Quantum++ v1.1

Generated by Doxygen 1.8.14

Contents

1	Qua	ntum++																	1
2	Nam	nespace	space Index 3																
	2.1	Names	space List									 	 		 	 	 		 3
3	Hier	archica	l Index																5
	3.1	Class	Hierarchy									 	 		 	 	 		 5
4	Clas	s Index																	7
	4.1	Class	List									 	 		 	 	 		 7
5	File	Index																	11
	5.1	File Lis	st									 	 		 	 	 		 11
6	Nam	nespace	Docume	nta	tion														13
	6.1	qpp Na	amespace	Re	ferer	nce .						 	 		 		 		 13
		6.1.1	Detailed	De	scrip	tion						 	 		 	 	 		 26
		6.1.2	Typedef	Dod	cume	entati	on .					 	 		 	 	 		 26
			6.1.2.1	bi	igint							 	 		 	 	 		 26
			6.1.2.2	bı	ra .							 	 		 	 	 		 26
			6.1.2.3	CI	mat							 	 		 	 	 		 27
			6.1.2.4	c	plx .							 	 		 	 	 		 27
			6.1.2.5	dı	mat							 	 		 		 		 27
			6.1.2.6	dy	yn_c	ol_ve	ect .					 	 		 	 	 		 27
			6.1.2.7	dy	yn_m	nat .						 	 		 	 	 		 27
			6.1.2.8	d١	vn ro	ow v	ect					 	 		 	 	 		 28

ii CONTENTS

	6.1.2.9	idx	28
	6.1.2.10	ket	28
	6.1.2.11	to_void	28
6.1.3	Function	Documentation	28
	6.1.3.1	absm()	28
	6.1.3.2	abssq() [1/3]	29
	6.1.3.3	abssq() [2/3]	29
	6.1.3.4	abssq() [3/3]	30
	6.1.3.5	adjoint()	30
	6.1.3.6	anticomm()	30
	6.1.3.7	apply() [1/5]	31
	6.1.3.8	apply() [2/5]	31
	6.1.3.9	apply() [3/5]	32
	6.1.3.10	apply() [4/5]	32
	6.1.3.11	apply() [5/5]	33
	6.1.3.12	applyCTRL() [1/2]	33
	6.1.3.13	applyCTRL() [2/2]	34
	6.1.3.14	applyQFT()	35
	6.1.3.15	applyTFQ()	35
	6.1.3.16	avg()	36
	6.1.3.17	bloch2rho()	36
	6.1.3.18	choi2kraus()	37
	6.1.3.19	choi2super()	37
	6.1.3.20	comm()	38
	6.1.3.21	complement()	38
	6.1.3.22	compperm()	38
	6.1.3.23	concurrence()	40
	6.1.3.24	conjugate()	40
	6.1.3.25	contfrac2x()	41
	6.1.3.26	convergents() [1/2]	41

6.1.3.27	convergents() [2/2]	42
6.1.3.28	cor()	42
6.1.3.29	cosm()	43
6.1.3.30	cov()	43
6.1.3.31	cwise()	43
6.1.3.32	det()	44
6.1.3.33	dirsum() [1/4]	44
6.1.3.34	dirsum() [2/4]	45
6.1.3.35	dirsum() [3/4]	45
6.1.3.36	dirsum() [4/4]	46
6.1.3.37	dirsumpow()	46
6.1.3.38	disp() [1/5]	47
6.1.3.39	disp() [2/5]	47
6.1.3.40	disp() [3/5]	47
6.1.3.41	disp() [4/5]	48
6.1.3.42	disp() [5/5]	48
6.1.3.43	egcd()	49
6.1.3.44	eig()	49
6.1.3.45	entanglement() [1/2]	50
6.1.3.46	entanglement() [2/2]	50
6.1.3.47	entropy() [1/2]	51
6.1.3.48	entropy() [2/2]	51
6.1.3.49	evals()	52
6.1.3.50	evects()	52
6.1.3.51	expm()	52
6.1.3.52	factors()	53
6.1.3.53	funm()	53
6.1.3.54	gcd() [1/2]	54
6.1.3.55	gcd() [2/2]	54
6.1.3.56	gconcurrence()	55

iv CONTENTS

6.1.3.57	grams() [1/3]	55
6.1.3.58	grams() [2/3]	55
6.1.3.59	grams() [3/3]	56
6.1.3.60	heig()	56
6.1.3.61	hevals()	57
6.1.3.62	hevects()	57
6.1.3.63	inverse()	58
6.1.3.64	invperm()	58
6.1.3.65	ip() [1/2]	58
6.1.3.66	ip() [2/2]	59
6.1.3.67	isprime()	59
6.1.3.68	kraus2choi()	60
6.1.3.69	kraus2super()	60
6.1.3.70	kron() [1/4]	61
6.1.3.71	kron() [2/4]	61
6.1.3.72	kron() [3/4]	62
6.1.3.73	kron() [4/4]	62
6.1.3.74	kronpow()	62
6.1.3.75	lcm() [1/2]	63
6.1.3.76	lcm() [2/2]	63
6.1.3.77	load()	64
6.1.3.78	loadMATLAB() [1/2]	64
6.1.3.79	loadMATLAB() [2/2]	65
6.1.3.80	logdet()	66
6.1.3.81	logm()	66
6.1.3.82	lognegativity() [1/2]	67
6.1.3.83	lognegativity() [2/2]	67
6.1.3.84	marginalX()	67
6.1.3.85	marginalY()	69
6.1.3.86	measure() [1/9]	69

6.1.3.87 measure() [2/9]	70
6.1.3.88 measure() [3/9]	70
6.1.3.89 measure() [4/9]	70
6.1.3.90 measure() [5/9]	'1
6.1.3.91 measure() [6/9]	2
6.1.3.92 measure() [7/9]	72
6.1.3.93 measure() [8/9]	73
6.1.3.94 measure() [9/9]	74
6.1.3.95 measure_seq() [1/2]	⁷ 4
6.1.3.96 measure_seq() [2/2]	75
6.1.3.97 mket() [1/2]	75
6.1.3.98 mket() [2/2]	76
6.1.3.99 modinv()	76
6.1.3.100 modmul()	7
6.1.3.101 modpow()	7
6.1.3.102 mprj() [1/2]	78
6.1.3.103 mprj() [2/2]	79
6.1.3.104 multiidx2n()	79
6.1.3.105 n2multiidx()	30
6.1.3.106 negativity() [1/2]	30
6.1.3.107 negativity() [2/2]	30
6.1.3.108 norm()	31
6.1.3.109 normalize()	31
6.1.3.110 omega()	32
6.1.3.111 operator""""_i()	32
6.1.3.112 powm()	32
6.1.3.113 prj()	33
6.1.3.114 prod() [1/3]	33
6.1.3.115 prod() [2/3]	34
6.1.3.116 prod() [3/3]	34

vi

6.1.3.117 ptrace() [1/2]
6.1.3.118 ptrace() [2/2]
6.1.3.119 ptrace1() [1/2]
6.1.3.120 ptrace1() [2/2]
6.1.3.121 ptrace2() [1/2]
6.1.3.122 ptrace2() [2/2]
6.1.3.123 ptranspose() [1/2]
6.1.3.124 ptranspose() [2/2]
6.1.3.125 QFT()
6.1.3.126 qmutualinfo() [1/2]
6.1.3.127 qmutualinfo() [2/2]
6.1.3.128 rand() [1/5] 90
6.1.3.129 rand() [2/5] 90
6.1.3.130 rand() [3/5] 91
6.1.3.131 rand() [4/5] 91
6.1.3.132 rand() [5/5]
6.1.3.133 randH()
6.1.3.134 randidx()
6.1.3.135 randket()
6.1.3.136 randkraus()
6.1.3.137 randn() [1/4] 94
6.1.3.138 randn() [2/4] 94
6.1.3.139 randn() [3/4]
6.1.3.140 randn() [4/4]
6.1.3.141 randperm()
6.1.3.142 randprime()
6.1.3.143 randprob()
6.1.3.144 randrho()
6.1.3.145 randU()
6.1.3.146 randV()

CONTENTS vii

6.1.3.147 renyi() [1/2]
6.1.3.148 renyi() [2/2]
6.1.3.149 reshape()
6.1.3.150 rho2bloch()
6.1.3.151 rho2pure()
6.1.3.152 save()
6.1.3.153 saveMATLAB() [1/2]
6.1.3.154 saveMATLAB() [2/2]
6.1.3.155 schatten()
6.1.3.156 schmidtA() [1/2]
6.1.3.157 schmidtA() [2/2]
6.1.3.158 schmidtB() [1/2]
6.1.3.159 schmidtB() [2/2]
6.1.3.160 schmidtcoeffs() [1/2]
6.1.3.161 schmidtcoeffs() [2/2]
6.1.3.162 schmidtprobs() [1/2]
6.1.3.163 schmidtprobs() [2/2]
6.1.3.164 sigma()
6.1.3.165 sinm()
6.1.3.166 spectralpowm()
6.1.3.167 sqrtm()
6.1.3.168 sum() [1/3]
6.1.3.169 sum() [2/3]
6.1.3.170 sum() [3/3]
6.1.3.171 super2choi()
6.1.3.172 svals()
6.1.3.173 svd()
6.1.3.174 svdU()
6.1.3.175 svdV()
6.1.3.176 syspermute() [1/2]

viii CONTENTS

		6.1.3.177	7 syspermute() [2/2]	112
		6.1.3.178	8 TFQ()	112
		6.1.3.179	9 trace()	113
		6.1.3.180	0 transpose()	113
		6.1.3.181	1 tsallis() [1/2]	113
		6.1.3.182	2 tsallis() [2/2]	114
		6.1.3.183	3 uniform()	114
		6.1.3.184	4 var()	115
		6.1.3.185	5 x2contfrac()	115
	6.1.4	Variable	Documentation	116
		6.1.4.1	chop	116
		6.1.4.2	ee	116
		6.1.4.3	eps	116
		6.1.4.4	idx_infty	116
		6.1.4.5	infty	116
		6.1.4.6	maxn	117
		6.1.4.7	pi	117
6.2	qpp::ex	ception N	lamespace Reference	117
	6.2.1	Detailed	Description	118
6.3	qpp::ex	perimenta	al Namespace Reference	119
	6.3.1	Detailed	Description	119
6.4	qpp::in	ternal Nan	mespace Reference	119
	6.4.1	Detailed	Description	120
	6.4.2	Function	Documentation	120
		6.4.2.1	check_cvector()	120
		6.4.2.2	check_dims()	120
		6.4.2.3	check_dims_match_cvect()	121
		6.4.2.4	check_dims_match_mat()	121
		6.4.2.5	check_dims_match_rvect()	121
		6.4.2.6	check_eq_dims()	121

		6.4.2.7	check_matching_sizes()	21
		6.4.2.8	check_no_duplicates()	21
		6.4.2.9	check_nonzero_size()	22
		6.4.2.10	check_perm()	22
		6.4.2.11	check_qubit_cvector()	22
		6.4.2.12	check_qubit_matrix()	22
		6.4.2.13	check_qubit_rvector()	22
		6.4.2.14	check_qubit_vector()	22
		6.4.2.15	check_rvector()	23
		6.4.2.16	check_square_mat()	23
		6.4.2.17	check_subsys_match_dims()	23
		6.4.2.18	check_vector()	23
		6.4.2.19	dirsum2()	23
		6.4.2.20	get_dim_subsys()	23
		6.4.2.21	get_num_subsys()	24
		6.4.2.22	kron2()	24
		6.4.2.23	multiidx2n()	24
		6.4.2.24	n2multiidx()	24
		6.4.2.25	variadic_vector_emplace() [1/2]	24
		6.4.2.26	variadic_vector_emplace() [2/2]	24
6.5	qpp::lit	erals Nam	espace Reference	25
	6.5.1	Function	Documentation	25
		6.5.1.1	operator"""" _bra()	25
		6.5.1.2	operator""""_i()	25
		6.5.1.3	operator"""" _ket()	26
		6.5.1.4	operator"""" _prj()	26

7	Clas	s Docu	mentation	129
	7.1	qpp::Bi	t_circuit Class Reference	129
		7.1.1	Detailed Description	131
		7.1.2	Constructor & Destructor Documentation	131
			7.1.2.1 Bit_circuit()	131
		7.1.3	Member Function Documentation	131
			7.1.3.1 CNOT()	131
			7.1.3.2 Dynamic_bitset()	132
			7.1.3.3 FRED()	132
			7.1.3.4 NOT()	132
			7.1.3.5 reset()	133
			7.1.3.6 SWAP()	133
			7.1.3.7 TOF()	133
			7.1.3.8 X()	134
		7.1.4	Member Data Documentation	134
			7.1.4.1 gate_count	134
	7.2	qpp::C	odes Class Reference	134
		7.2.1	Detailed Description	135
		7.2.2	Member Enumeration Documentation	135
			7.2.2.1 Type	136
		7.2.3	Constructor & Destructor Documentation	136
			7.2.3.1 Codes()	136
			7.2.3.2 ~Codes()	136
		7.2.4	Member Function Documentation	136
			7.2.4.1 codeword()	136
		7.2.5	Friends And Related Function Documentation	137
			7.2.5.1 internal::Singleton < const Codes >	137
	7.3	qpp::ex	cception::CustomException Class Reference	137
		7.3.1	Detailed Description	138
		7.3.2	Constructor & Destructor Documentation	138

CONTENTS xi

		7.3.2.1	CustomException()	. 139
	7.3.3	Member F	Function Documentation	. 139
		7.3.3.1	type_description()	. 139
	7.3.4	Member [Data Documentation	. 139
		7.3.4.1	what	. 139
7.4	qpp::ex	xception::D	imsInvalid Class Reference	. 140
	7.4.1	Detailed [Description	. 141
	7.4.2	Member F	Function Documentation	. 141
		7.4.2.1	Exception()	. 141
		7.4.2.2	type_description()	. 141
7.5	qpp::ex	xception::D	imsMismatchCvector Class Reference	. 142
	7.5.1	Detailed [Description	. 143
	7.5.2	Member F	Function Documentation	. 143
		7.5.2.1	Exception()	. 143
		7.5.2.2	type_description()	. 143
7.6	qpp::ex	xception::D	imsMismatchMatrix Class Reference	. 144
	7.6.1	Detailed [Description	. 145
	7.6.2	Member F	Function Documentation	. 145
		7.6.2.1	Exception()	. 145
		7.6.2.2	type_description()	. 145
7.7	qpp::ex	xception::D	imsMismatchRvector Class Reference	. 146
	7.7.1	Detailed [Description	. 147
	7.7.2	Member F	Function Documentation	. 147
		7.7.2.1	Exception()	. 147
		7.7.2.2	type_description()	. 147
7.8	qpp::ex	xception::D	imsMismatchVector Class Reference	. 148
	7.8.1	Detailed [Description	. 149
	7.8.2	Member F	Function Documentation	. 149
		7.8.2.1	Exception()	. 149
		7.8.2.2	type_description()	. 149

xii CONTENTS

7.9	qpp::ex	cception::DimsNotEqual Class Reference
	7.9.1	Detailed Description
	7.9.2	Member Function Documentation
		7.9.2.1 Exception()
		7.9.2.2 type_description()
7.10	qpp::in	ternal::Display_Impl_ Struct Reference
	7.10.1	Member Function Documentation
		7.10.1.1 display_impl_()
7.11	qpp::ex	cception::Duplicates Class Reference
	7.11.1	Detailed Description
	7.11.2	Member Function Documentation
		7.11.2.1 Exception()
		7.11.2.2 type_description()
7.12	qpp::D	ynamic_bitset Class Reference
	7.12.1	Detailed Description
	7.12.2	Member Typedef Documentation
		7.12.2.1 storage_type
		7.12.2.2 value_type
	7.12.3	Constructor & Destructor Documentation
		7.12.3.1 Dynamic_bitset()
		7.12.3.2 ~Dynamic_bitset()
	7.12.4	Member Function Documentation
		7.12.4.1 all()
		7.12.4.2 any()
		7.12.4.3 count()
		7.12.4.4 data()
		7.12.4.5 display()
		7.12.4.6 flip() [1/2]
		7.12.4.7 flip() [2/2]
		7.12.4.8 get()

CONTENTS xiii

		7.12.4.9 index_()	60
		7.12.4.10 none()	61
		7.12.4.11 offset_()	61
		7.12.4.12 operator"!=()	61
		7.12.4.13 operator-()	62
		7.12.4.14 operator==()	62
		7.12.4.15 rand() [1/2]	62
		7.12.4.16 rand() [2/2]	63
		7.12.4.17 reset() [1/2]	63
		7.12.4.18 reset() [2/2]	63
		7.12.4.19 set() [1/2]	64
		7.12.4.20 set() [2/2]	64
		7.12.4.21 size()	64
		7.12.4.22 storage_size()	64
		7.12.4.23 to_string()	65
	7.12.5	Member Data Documentation	65
		7.12.5.1 N	65
		7.12.5.2 storage_size	65
		7.12.5.3 v	66
7.13	qpp::ex	cception::Exception Class Reference	66
	7.13.1	Detailed Description	68
	7.13.2	Constructor & Destructor Documentation	69
		7.13.2.1 Exception()	69
	7.13.3	Member Function Documentation	69
		7.13.3.1 type_description()	69
		7.13.3.2 what()	70
	7.13.4	Member Data Documentation	70
		7.13.4.1 msg	70
		7.13.4.2 where	70
7.14	qpp::Bi	it_circuit::Gate_count Struct Reference	70

xiv CONTENTS

	7.14.1	Member Data Documentation
		7.14.1.1 CNOT
		7.14.1.2 FRED
		7.14.1.3 NOT
		7.14.1.4 SWAP
		7.14.1.5 TOF
		7.14.1.6 X
7.15	qpp::Ga	ates Class Reference
	7.15.1	Detailed Description
	7.15.2	Constructor & Destructor Documentation
		7.15.2.1 Gates()
		7.15.2.2 ~Gates()
	7.15.3	Member Function Documentation
		7.15.3.1 CTRL()
		7.15.3.2 expandout() [1/3]
		7.15.3.3 expandout() [2/3]
		7.15.3.4 expandout() [3/3]
		7.15.3.5 Fd()
		7.15.3.6 get_name()
		7.15.3.7 ld()
		7.15.3.8 MODMUL()
		7.15.3.9 Rn()
		7.15.3.10 RX()
		7.15.3.11 RY()
		7.15.3.12 RZ()
		7.15.3.13 SWAPd()
		7.15.3.14 Xd()
		7.15.3.15 Zd()
	7.15.4	Friends And Related Function Documentation
		7.15.4.1 internal::Singleton < const Gates >

CONTENTS xv

7.1	.5 Member Data Documentation
	7.15.5.1 CNOT
	7.15.5.2 CNOTba
	7.15.5.3 CZ
	7.15.5.4 FRED
	7.15.5.5 H
	7.15.5.6 ld2
	7.15.5.7 S
	7.15.5.8 SWAP
	7.15.5.9 T
	7.15.5.10 TOF
	7.15.5.11 X
	7.15.5.12 Y
	7.15.5.13 Z
7.16 qpp	:QCircuitDescription::GateStep Struct Reference
7.10	.1 Detailed Description
7.10	.2 Constructor & Destructor Documentation
	7.16.2.1 GateStep() [1/2]
	7.16.2.2 GateStep() [2/2]
7.10	3 Member Data Documentation
	7.16.3.1 ctrl
	7.16.3.2 gate
	7.16.3.3 gate_type
	7.16.3.4 name
	7.16.3.5 target
7.17 qpp	:IDisplay Class Reference
7.1	.1 Detailed Description
7.1	.2 Constructor & Destructor Documentation
	7.17.2.1 IDisplay() [1/3]
	7.17.2.2 IDisplay() [2/3]

xvi CONTENTS

		7.17.2.3 IDisplay() [3/3]
		7.17.2.4 ~IDisplay()
	7.17.3	Member Function Documentation
		7.17.3.1 display()
		7.17.3.2 operator=() [1/2]
		7.17.3.3 operator=() [2/2]
	7.17.4	Friends And Related Function Documentation
		7.17.4.1 operator<<
7.18	qpp::lJ	SON Class Reference
	7.18.1	Detailed Description
	7.18.2	Constructor & Destructor Documentation
		7.18.2.1 IJSON() [1/3]
		7.18.2.2 IJSON() [2/3]
		7.18.2.3 IJSON() [3/3]
		7.18.2.4 ~IJSON()
	7.18.3	Member Function Documentation
		7.18.3.1 operator=() [1/2]
		7.18.3.2 operator=() [2/2]
		7.18.3.3 to_JSON()
7.19	qpp::ln	it Class Reference
	7.19.1	Detailed Description
	7.19.2	Constructor & Destructor Documentation
		7.19.2.1 Init()
		7.19.2.2 ~Init()
	7.19.3	Friends And Related Function Documentation
		7.19.3.1 internal::Singleton < const Init >
7.20	qpp::ex	cception::InvalidIterator Class Reference
	7.20.1	Detailed Description
	7.20.2	Member Function Documentation
		7.20.2.1 Exception()

CONTENTS xvii

		7.20.2.2 type_description()	197
7.21	qpp::int	ternal::IOManipEigen Class Reference	197
	7.21.1	Constructor & Destructor Documentation	199
		7.21.1.1 IOManipEigen() [1/2]	199
		7.21.1.2 IOManipEigen() [2/2]	199
	7.21.2	Member Function Documentation	199
		7.21.2.1 display()	199
	7.21.3	Member Data Documentation	199
		7.21.3.1 A	199
		7.21.3.2 chop	200
7.22	qpp::int	ternal::IOManipPointer< PointerType > Class Template Reference	200
	7.22.1	Constructor & Destructor Documentation	201
		7.22.1.1 IOManipPointer() [1/2]	201
		7.22.1.2 IOManipPointer() [2/2]	201
	7.22.2	Member Function Documentation	201
		7.22.2.1 display()	202
		7.22.2.2 operator=()	202
	7.22.3	Member Data Documentation	202
		7.22.3.1 end	202
		7.22.3.2 N	202
		7.22.3.3 p	202
		7.22.3.4 separator	203
		7.22.3.5 start	203
7.23	qpp::int	ternal::IOManipRange < InputIterator > Class Template Reference	203
	7.23.1	Constructor & Destructor Documentation	204
		7.23.1.1 IOManipRange() [1/2]	205
		7.23.1.2 IOManipRange() [2/2]	205
	7.23.2	Member Function Documentation	205
		7.23.2.1 display()	205
		7.23.2.2 operator=()	205

xviii CONTENTS

	7.23.3	Member Data Documentation	05
		7.23.3.1 end	06
		7.23.3.2 first	06
		7.23.3.3 last	06
		7.23.3.4 separator	06
		7.23.3.5 start	06
7.24	qpp::is_	_complex< T > Struct Template Reference	07
	7.24.1	Detailed Description	07
7.25	qpp::is_	_complex< std::complex< T > > Struct Template Reference	80
	7.25.1	Detailed Description	80
7.26	qpp::is_	_iterable < T, typename > Struct Template Reference	09
	7.26.1	Detailed Description	09
7.27		_iterable $<$ T, to_void $<$ decltype(std::declval $<$ T $>$ ().begin()), decltype(std::declval $<$ T d()), decltype(*(std::declval $<$ T $>$ ().begin()))> $>$ Struct Template Reference	10
	7.27.1	Detailed Description	11
7.28	qpp::is_	_matrix_expression< Derived > Struct Template Reference	11
	7.28.1	Detailed Description	11
7.29	qpp::Q0	CircuitDescription::iterator Class Reference	12
	7.29.1	Detailed Description	13
	7.29.2	Member Typedef Documentation	13
		7.29.2.1 difference_type	13
		7.29.2.2 iterator_category	13
		7.29.2.3 pointer	13
		7.29.2.4 reference	14
		7.29.2.5 value_type	14
	7.29.3	Constructor & Destructor Documentation	14
		7.29.3.1 iterator() [1/2]	14
		7.29.3.2 iterator() [2/2]	14
	7.29.4	Member Function Documentation	14
		7.29.4.1 operator"!=()	14
		7.29.4.2 operator*()	15

CONTENTS xix

		7.29.4.3 operator++() [1/2]	15
		7.29.4.4 operator++() [2/2]	15
		7.29.4.5 operator=()	16
		7.29.4.6 operator==()	16
		7.29.4.7 set_begin_()	16
		7.29.4.8 set_end_()	16
	7.29.5	Member Data Documentation	17
		7.29.5.1 elem	17
		7.29.5.2 qcd	17
7.30	qpp::ma	ake_void< Ts > Struct Template Reference	17
	7.30.1	Detailed Description	17
	7.30.2	Member Typedef Documentation	18
		7.30.2.1 type	18
7.31	qpp::ex	cception::MatrixMismatchSubsys Class Reference	18
	7.31.1	Detailed Description	19
	7.31.2	Member Function Documentation	19
		7.31.2.1 Exception()	19
		7.31.2.2 type_description()	20
7.32	qpp::ex	cception::MatrixNotCvector Class Reference	20
	7.32.1	Detailed Description	21
	7.32.2	Member Function Documentation	21
		7.32.2.1 Exception()	21
		7.32.2.2 type_description()	22
7.33	qpp::ex	cception::MatrixNotRvector Class Reference	22
	7.33.1	Detailed Description	23
	7.33.2	Member Function Documentation	23
		7.33.2.1 Exception()	23
		7.33.2.2 type_description()	24
7.34	qpp::ex	cception::MatrixNotSquare Class Reference	24
	7.34.1	Detailed Description	25

	7.34.2	Member Function Documentation	25
		7.34.2.1 Exception()	25
		7.34.2.2 type_description()	26
7.35	qpp::ex	cception::MatrixNotSquareNorCvector Class Reference	26
	7.35.1	Detailed Description	27
	7.35.2	Member Function Documentation	27
		7.35.2.1 Exception()	27
		7.35.2.2 type_description()	28
7.36	qpp::ex	cception::MatrixNotSquareNorRvector Class Reference	28
	7.36.1	Detailed Description	29
	7.36.2	Member Function Documentation	29
		7.36.2.1 Exception()	29
		7.36.2.2 type_description()	30
7.37	qpp::ex	cception::MatrixNotSquareNorVector Class Reference	30
	7.37.1	Detailed Description	31
	7.37.2	Member Function Documentation	31
		7.37.2.1 Exception()	31
		7.37.2.2 type_description()	32
7.38	qpp::ex	cception::MatrixNotVector Class Reference	32
	7.38.1	Detailed Description	33
	7.38.2	Member Function Documentation	33
		7.38.2.1 Exception()	33
		7.38.2.2 type_description()	34
7.39	qpp::Q	CircuitDescription::MeasureStep Struct Reference	34
	7.39.1	Detailed Description	35
	7.39.2	Constructor & Destructor Documentation	35
		7.39.2.1 MeasureStep() [1/2]	35
		7.39.2.2 MeasureStep() [2/2]	35
	7.39.3	Member Data Documentation	36
		7.39.3.1 c_reg	36

CONTENTS xxi

		7.39.3.2 mats	23
		7.39.3.3 measurement_type	23
		7.39.3.4 name	23
		7.39.3.5 target	23
7.40	qpp::ex	ception::NoCodeword Class Reference	23
	7.40.1	Detailed Description	23
	7.40.2	Member Function Documentation	23
		7.40.2.1 Exception()	23
		7.40.2.2 type_description()	23
7.41	qpp::No	iseBase< T > Class Template Reference	23
	7.41.1	Detailed Description	24
	7.41.2	Member Typedef Documentation	24
		7.41.2.1 noise_type	24
	7.41.3	Constructor & Destructor Documentation	24
		7.41.3.1 NoiseBase() [1/2]	24
		7.41.3.2 NoiseBase() [2/2]	24
		7.41.3.3 ~NoiseBase()	24
	7.41.4	Member Function Documentation	24
		7.41.4.1 compute_probs_()	24
		7.41.4.2 compute_state_()	24
		7.41.4.3 get_d()	24
		7.41.4.4 get_Ks()	24
		7.41.4.5 get_last_idx()	24
		7.41.4.6 get_last_K()	24
		7.41.4.7 get_last_p()	24
		7.41.4.8 get_probs()	24
		7.41.4.9 operator()() [1/2]	24
		7.41.4.10 operator()() [2/2]	24
	7.41.5	Member Data Documentation	24
		7.41.5.1 d	24

xxii CONTENTS

		7.41.5.2	ge	enerate	ed					 	 	 	 	 	 	 245
		7.41.5.3	i_							 	 	 	 	 	 	 246
		7.41.5.4	K	s						 	 	 	 	 	 	 246
		7.41.5.5	pr	obs_						 	 	 	 	 	 	 246
7.42	qpp::No	oiseType C	Clas	ss Refe	erenc	ce .				 	 	 	 	 	 	 246
	7.42.1	Detailed I	De	scriptio	on .					 	 	 	 	 	 	 246
7.43	qpp::ex	ception::N	VotE	3ipartit	te Cla	ass F	Refere	ence		 	 	 	 	 	 	 247
	7.43.1	Detailed I	De	scriptio	on .					 	 	 	 	 	 	 248
	7.43.2	Member I	Fur	nction	Docu	umer	ntation	n .		 	 	 	 	 	 	 248
		7.43.2.1	E	xceptio	on() .					 	 	 	 	 	 	 248
		7.43.2.2	ty	pe_de	scrip	otion(()			 	 	 	 	 	 	 248
7.44	qpp::ex	ception::N	Votl	mplem	nente	ed Cla	ass P	Refere	ence	 	 	 	 	 	 	 249
	7.44.1	Detailed I	De	scriptio	on .					 	 	 	 	 	 	 250
	7.44.2	Member I	Fur	nction	Docu	umer	ntation	n .		 	 	 	 	 	 	 250
		7.44.2.1	E:	xceptio	on() .					 	 	 	 	 	 	 250
		7.44.2.2	ty	pe_de	scrip	otion(()			 	 	 	 	 	 	 250
7.45	qpp::ex	ception::N	Vot(QubitC	vecto	or Cl	ass F	Refere	ence	 	 	 	 	 	 	 251
	7.45.1	Detailed I	De	scriptio	on .					 	 	 	 	 	 	 252
	7.45.2	Member I	Fur	nction	Docu	umer	ntation	n .		 	 	 	 	 	 	 252
		7.45.2.1	E	xceptio	on() .					 	 	 	 	 	 	 252
		7.45.2.2	ty	pe_de	scrip	otion(()			 	 	 	 	 	 	 252
7.46	qpp::ex	ception::N	Vot(QubitM	1atrix	Clas	ss Re	eferer	nce .	 	 	 	 	 	 	 253
	7.46.1	Detailed I	De	scriptio	on .					 	 	 	 	 	 	 254
	7.46.2	Member I	Fur	nction	Docu	umer	ntatio	n .		 	 	 	 	 	 	 254
		7.46.2.1	E	xceptio	on() .					 	 	 	 	 	 	 254
		7.46.2.2	ty	pe_de	scrip	otion(()			 	 	 	 	 	 	 254
7.47	qpp::ex	ception::N	Vot(QubitR	lvecto	or Cl	ass F	Refere	ence	 	 	 	 	 	 	 255
	7.47.1	Detailed I	De	scriptio	on .					 	 	 	 	 	 	 256
	7.47.2	Member I	Fur	nction	Docu	umer	ntatio	n .		 	 	 	 	 	 	 256
		7.47.2.1	E	xceptic	on() .					 	 	 	 	 	 	 256

CONTENTS xxiii

		7.47.2.2 type_description()	 256
7.48	qpp::ex	ception::NotQubitSubsys Class Reference	 257
	7.48.1	Detailed Description	 258
	7.48.2	Member Function Documentation	 258
		7.48.2.1 Exception()	 258
		7.48.2.2 type_description()	 258
7.49	qpp::ex	ception::NotQubitVector Class Reference	 259
	7.49.1	Detailed Description	 260
	7.49.2	Member Function Documentation	 260
		7.49.2.1 Exception()	 260
		7.49.2.2 type_description()	 260
7.50	qpp::ex	ception::OutOfRange Class Reference	 261
	7.50.1	Detailed Description	 262
	7.50.2	Member Function Documentation	 262
		7.50.2.1 Exception()	 262
		7.50.2.2 type_description()	 262
7.51	qpp::ex	ception::PermInvalid Class Reference	 263
	7.51.1	Detailed Description	 264
	7.51.2	Member Function Documentation	 264
		7.51.2.1 Exception()	 264
		7.51.2.2 type_description()	 264
7.52	qpp::ex	ception::PermMismatchDims Class Reference	 265
	7.52.1	Detailed Description	 266
	7.52.2	Member Function Documentation	 266
		7.52.2.1 Exception()	 266
		7.52.2.2 type_description()	 266
7.53	qpp::Q	Circuit Class Reference	 267
	7.53.1	Detailed Description	 268
	7.53.2	Constructor & Destructor Documentation	 269
		7.53.2.1 QCircuit() [1/2]	 269

xxiv CONTENTS

		7.53.2.2	C	QC	ircu	it() [[2/	′2]							 					 	 	 269
		7.53.2.3	^	~Q	(Circ	cuit()) .								 					 	 	 269
7.5	53.3	Member F	Fu	unc	tion	ı Do	cur	me	enta	atio	n				 					 	 	 269
		7.53.3.1	d	disp	olay	() .									 					 	 	 270
		7.53.3.2	е	exe	cute) ()e	1/:	2]							 					 	 	 270
		7.53.3.3	е	exe	cute	∋() [2/:	2]							 					 	 	 270
		7.53.3.4	g	get	_cir	cuit_	_de	esc	rip	tior	า()				 					 	 	 271
		7.53.3.5	g	get	_dit	() .									 					 	 	 271
		7.53.3.6	g	get	_dit	s() .									 					 	 	 271
		7.53.3.7	g	get	_me	asu	rec	d()	[1	./2] .				 					 	 	 271
		7.53.3.8	g	get	_me	asu	rec	d()	[2	2/2] .				 					 	 	 272
		7.53.3.9	g	get	_no	t_me	eas	sur	red	()					 					 	 	 272
		7.53.3.10) g	get	_pro	obs()) .								 					 	 	 272
		7.53.3.11	1 g	get	_ps	i() .									 					 	 	 273
		7.53.3.12	2 g	get	_ref	_psi	i()								 					 	 	 273
		7.53.3.13	3 g	get	_rel	ative	e_p	os	s_())					 					 	 	 273
		7.53.3.14	4 r	es	et()										 					 	 	 273
		7.53.3.15	5 s	set	_dit	() .									 					 	 	 274
		7.53.3.16	6 s	set_	_me	asu	rec)_t	() .						 					 	 	 275
		7.53.3.17	7 to	0	JSC	ON()									 					 	 	 275
7.5	53.4	Member I	Da	ata	. Do	cum	en	tat	lior	١.					 					 	 	 275
		7.53.4.1	d	dits											 					 	 	 276
		7.53.4.2	p	oro	bs_										 					 	 	 276
		7.53.4.3	p	osi_											 					 	 	 276
		7.53.4.4	q	qcd	<u> </u>										 					 	 	 276
		7.53.4.5	S	sub	sys										 					 	 	 276
7.54 qp	p::QC	CircuitDes	scr	ripti	ion	Clas	s F	Ref	fer	enc	е				 					 	 	 277
7.5	54.1	Detailed I	De	esc	cript	ion								-	 	 				 	 	 281
7.5	54.2	Member ⁻	Ту	/pe	def	Doc	um	ner	nta	tior	١.				 					 	 	 281
		7.54.2.1	С	con	ıst_i	itera	tor								 					 	 	 281

CONTENTS xxv

7.54.3	Member E	Eni	umer	ation	n Do	cun	nent	tatio	on		 			 					281
	7.54.3.1	G	ateTy	ype							 			 					281
	7.54.3.2	M	leasu	ıreTy	ype .						 			 					282
	7.54.3.3	S	tepTy	/pe							 			 					282
7.54.4	Construct	tor	& De	estru	uctor	Do	cum	nen	tati	on	 			 					282
	7.54.4.1	Q	Circu	uitDe	escri	ptio	n()				 			 					282
	7.54.4.2	~	⁄QCir	rcuitl	Desc	cript	ion(() .			 			 					283
7.54.5	Member F	Fur	nctio	n Do	cum	ent	atio	n			 			 					283
	7.54.5.1	be	egin() [1,	/2]						 			 					283
	7.54.5.2	be	egin() [2,	/2]						 			 					283
	7.54.5.3	ck	oegin	1()							 			 					284
	7.54.5.4	c(CTRL	L () [1/4]	١					 			 					284
	7.54.5.5	c(CTRL	L () [2/4]	١					 			 					284
	7.54.5.6	c(CTRL	L () [3/4]	١					 			 					285
	7.54.5.7	c(CTRL	_ () [4/4]	١					 			 					285
	7.54.5.8	c(CTRL	cu	ıston	n() .					 			 					286
	7.54.5.9	CE	end()								 			 					286
	7.54.5.10	C	TRL(() [1	/4]						 			 					286
	7.54.5.11	ı C	TRL(() [2	/4]						 			 					287
	7.54.5.12	2 C	TRL(() [3	/4]						 			 					287
	7.54.5.13	3 C	TRL(() [4	/4]						 			 					288
	7.54.5.14	1 C	TRL _.	_cus	tom	()					 			 					288
	7.54.5.15	5 di	isplay	y()							 			 					289
	7.54.5.16	6 er	nd()	[1/2	2].						 			 					289
	7.54.5.17	7 er	nd()	[2/2	2].						 			 					290
	7.54.5.18	3 ga	ate()	[1/:	3] .						 			 					290
	7.54.5.19	e ga	ate()	[2/	3] .						 			 					290
	7.54.5.20) ga	ate()	[3/:	3] .						 			 					291
	7.54.5.21	l ga	ate_c	custo	om()						 			 					291
	7.54.5.22	2 ga	ate_f	an()	[1/	3].					 			 					292

xxvi CONTENTS

	7.54.5.23 gate_fan() [2/3]	292
	7.54.5.24 gate_fan() [3/3]	292
	7.54.5.25 get_d()	293
	7.54.5.26 get_gate_count()	293
	7.54.5.27 get_gates()	293
	7.54.5.28 get_measured() [1/2]	293
	7.54.5.29 get_measured() [2/2]	294
	7.54.5.30 get_measurement_count()	294
	7.54.5.31 get_measurements()	294
	7.54.5.32 get_name()	295
	7.54.5.33 get_nc()	295
	7.54.5.34 get_non_measured()	295
	7.54.5.35 get_nq()	295
	7.54.5.36 get_step_count()	296
	7.54.5.37 measureV() [1/2]	296
	7.54.5.38 measureV() [2/2]	296
	7.54.5.39 measureZ()	297
	7.54.5.40 QFT()	297
	7.54.5.41 TFQ()	297
	7.54.5.42 to_JSON()	298
7.54.6	Friends And Related Function Documentation	298
	7.54.6.1 operator<< [1/4]	298
	7.54.6.2 operator<< [2/4]	299
	7.54.6.3 operator<< [3/4]	299
	7.54.6.4 operator<< [4/4]	299
7.54.7	Member Data Documentation	300
	7.54.7.1 d	300
	7.54.7.2 gates	300
	7.54.7.3 measured	300
	7.54.7.4 measurements	300

CONTENTS xxvii

		7.54.7.5 name	01
		7.54.7.6 nc	01
		7.54.7.7 nq	01
		7.54.7.8 step_types	01
7.55	qpp::Q	ubitAmplitudeDampingNoise Class Reference	02
	7.55.1	Detailed Description	03
	7.55.2	Constructor & Destructor Documentation	03
		7.55.2.1 QubitAmplitudeDampingNoise()	03
7.56	qpp::Q	ubitBitFlipNoise Class Reference	03
	7.56.1	Detailed Description	04
	7.56.2	Constructor & Destructor Documentation	04
		7.56.2.1 QubitBitFlipNoise()	04
7.57	qpp::Qı	ubitBitPhaseFlipNoise Class Reference	05
	7.57.1	Detailed Description	06
	7.57.2	Constructor & Destructor Documentation	06
		7.57.2.1 QubitBitPhaseFlipNoise()	06
7.58	qpp::Qı	ubitDepolarizingNoise Class Reference	06
	7.58.1	Detailed Description	07
	7.58.2	Constructor & Destructor Documentation	07
		7.58.2.1 QubitDepolarizingNoise()	07
7.59	qpp::Q	ubitPhaseDampingNoise Class Reference	808
	7.59.1	Detailed Description	809
	7.59.2	Constructor & Destructor Documentation	09
		7.59.2.1 QubitPhaseDampingNoise()	09
7.60	qpp::Q	ubitPhaseFlipNoise Class Reference	09
	7.60.1	Detailed Description	10
	7.60.2	Constructor & Destructor Documentation	10
		7.60.2.1 QubitPhaseFlipNoise()	10
7.61	qpp::ex	ception::QuditAlreadyMeasured Class Reference	311
	7.61.1	Detailed Description	312

xxviii CONTENTS

	7.61.2	Member Function Documentation
		7.61.2.1 Exception()
		7.61.2.2 type_description()
7.62	qpp::Qı	uditDepolarizingNoise Class Reference
	7.62.1	Detailed Description
	7.62.2	Constructor & Destructor Documentation
		7.62.2.1 QuditDepolarizingNoise()
	7.62.3	Member Function Documentation
		7.62.3.1 fill_Ks_()
		7.62.3.2 fill_probs_()
7.63	qpp::Ra	andomDevices Class Reference
	7.63.1	Detailed Description
	7.63.2	Constructor & Destructor Documentation
		7.63.2.1 RandomDevices()
		7.63.2.2 ~RandomDevices()
	7.63.3	Member Function Documentation
		7.63.3.1 get_prng()
		7.63.3.2 load()
		7.63.3.3 save()
	7.63.4	Friends And Related Function Documentation
		7.63.4.1 internal::Singleton < RandomDevices >
	7.63.5	Member Data Documentation
		7.63.5.1 prng
		7.63.5.2 rd
7.64	qpp::int	ternal::Singleton< T > Class Template Reference
	7.64.1	Detailed Description
	7.64.2	Constructor & Destructor Documentation
		7.64.2.1 Singleton() [1/2]
		7.64.2.2 Singleton() [2/2] 32
		7.64.2.3 ~Singleton()

CONTENTS xxix

	7.64.3	Member Function Documentation
		7.64.3.1 get_instance()
		7.64.3.2 get_thread_local_instance()
		7.64.3.3 operator=()
7.65	qpp::ex	cception::SizeMismatch Class Reference
	7.65.1	Detailed Description
	7.65.2	Member Function Documentation
		7.65.2.1 Exception()
		7.65.2.2 type_description()
7.66	qpp::No	oiseType::StateDependent Class Reference
	7.66.1	Detailed Description
7.67	qpp::No	oiseType::StateIndependent Class Reference
	7.67.1	Detailed Description
7.68	qpp::St	tates Class Reference
	7.68.1	Detailed Description
	7.68.2	Constructor & Destructor Documentation
		7.68.2.1 States()
		7.68.2.2 ~States()
	7.68.3	Member Function Documentation
		7.68.3.1 jn()
		7.68.3.2 mes()
		7.68.3.3 minus()
		7.68.3.4 one()
		7.68.3.5 plus()
		7.68.3.6 zero()
	7.68.4	Friends And Related Function Documentation
		7.68.4.1 internal::Singleton < const States >
	7.68.5	Member Data Documentation
		7.68.5.1 b00
		7.68.5.2 b01

		7.68.5.3 b10
		7.68.5.4 b11
		7.68.5.5 GHZ
		7.68.5.6 pb00
		7.68.5.7 pb01
		7.68.5.8 pb10
		7.68.5.9 pb11
		7.68.5.10 pGHZ
		7.68.5.11 pW
		7.68.5.12 px0
		7.68.5.13 px1
		7.68.5.14 py0
		7.68.5.15 py1
		7.68.5.16 pz0
		7.68.5.17 pz1
		7.68.5.18 W
		7.68.5.19 x0
		7.68.5.20 x1
		7.68.5.21 y0
		7.68.5.22 y1
		7.68.5.23 z0
		7.68.5.24 z1
7.69	qpp::ex	ception::SubsysMismatchDims Class Reference
	7.69.1	Detailed Description
	7.69.2	Member Function Documentation
		7.69.2.1 Exception()
		7.69.2.2 type_description()
7.70	qpp::Ti	mer< T, CLOCK_T > Class Template Reference
	7.70.1	Detailed Description
	7.70.2	Constructor & Destructor Documentation

CONTENTS xxxi

		7.70.2.1 Timer() [1/3]	37
		7.70.2.2 Timer() [2/3]	38
		7.70.2.3 Timer() [3/3]	38
		7.70.2.4 ~Timer()	38
	7.70.3	Member Function Documentation	38
		7.70.3.1 display()	38
		7.70.3.2 get_duration()	39
		7.70.3.3 operator=() [1/2]	39
		7.70.3.4 operator=() [2/2]	39
		7.70.3.5 tic()	40
		7.70.3.6 tics()	40
		7.70.3.7 toc()	40
	7.70.4	Member Data Documentation	40
		7.70.4.1 end	40
		7.70.4.2 start	41
7.71	qpp::ex	cception::TypeMismatch Class Reference	41
	7.71.1	Detailed Description	42
	7.71.2	Member Function Documentation	42
		7.71.2.1 Exception()	42
		7.71.2.2 type_description()	43
7.72	qpp::ex	cception::UndefinedType Class Reference	43
	7.72.1	Detailed Description	44
	7.72.2	Member Function Documentation	44
		7.72.2.1 Exception()	44
		7.72.2.2 type_description()	45
7.73	qpp::ex	cception::Unknown Class Reference	45
	7.73.1	Detailed Description	46
	7.73.2	Member Function Documentation	46
		7.73.2.1 Exception()	46
		7.73.2.2 type_description()	47

xxxii CONTENTS

	7.74	qpp::Q	CircuitDescription::iterator::value_type_ Struct Reference
		7.74.1	Constructor & Destructor Documentation
			7.74.1.1 value_type_() [1/2]
			7.74.1.2 value_type_() [2/2]
		7.74.2	Member Function Documentation
			7.74.2.1 display()
			7.74.2.2 operator=()
		7.74.3	Member Data Documentation
			7.74.3.1 gates_ip
			7.74.3.2 ip
			7.74.3.3 measurements_ip
			7.74.3.4 type
			7.74.3.5 value_type_qcd
	7.75	qpp::ex	cception::ZeroSize Class Reference
		7.75.1	Detailed Description
		7.75.2	Member Function Documentation
			7.75.2.1 Exception()
			7.75.2.2 type_description()
8	File I	Docume	entation 353
	8.1	classes	s/circuits.h File Reference
		8.1.1	Detailed Description
	8.2	classes	s/codes.h File Reference
		8.2.1	Detailed Description
	8.3	classes	s/exception.h File Reference
		8.3.1	Detailed Description
	8.4	classes	s/gates.h File Reference
		8.4.1	Detailed Description
	8.5	classes	s/idisplay.h File Reference
		8.5.1	Detailed Description
	8.6	classes	S/init.h File Reference

CONTENTS xxxiii

	8.6.1	Detailed Description		 	 	 	 	359
8.7	classes	/noise.h File Reference		 	 	 	 	359
	8.7.1	Detailed Description		 	 	 	 	360
8.8	classes	/random_devices.h File	Reference	 	 	 	 	360
	8.8.1	Detailed Description		 	 	 	 	360
8.9	classes	/reversible.h File Refer	ence	 	 	 	 	361
	8.9.1	Detailed Description		 	 	 	 	361
8.10	classes	states.h File Referenc	e	 	 	 	 	361
	8.10.1	Detailed Description		 	 	 	 	362
8.11	classes	/timer.h File Reference		 	 	 	 	362
	8.11.1	Detailed Description		 	 	 	 	363
8.12	constar	nts.h File Reference .		 	 	 	 	363
	8.12.1	Detailed Description		 	 	 	 	364
8.13	entang	ement.h File Reference		 	 	 	 	364
	8.13.1	Detailed Description		 	 	 	 	366
8.14	entropi	es.h File Reference .		 	 	 	 	366
	8.14.1	Detailed Description		 	 	 	 	367
8.15	experin	nental/experimental.h F	ile Reference	 	 	 	 	367
	8.15.1	Detailed Description		 	 	 	 	367
8.16	function	ns.h File Reference		 	 	 	 	367
	8.16.1	Detailed Description		 	 	 	 	372
8.17	input_c	utput.h File Reference		 	 	 	 	372
	8.17.1	Detailed Description		 	 	 	 	373
8.18	instrum	ents.h File Reference		 	 	 	 	373
	8.18.1	Detailed Description		 	 	 	 	374
8.19	interna	/classes/iomanip.h File	Reference .	 	 	 	 	374
	8.19.1	Detailed Description		 	 	 	 	375
8.20	interna	/classes/singleton.h Fil	e Reference	 	 	 	 	375
	8.20.1	Detailed Description		 	 	 	 	376
8.21	interna	/util.h File Reference .		 	 	 	 	376

	8.21.1 Detailed Description	377
8.22	MATLAB/matlab.h File Reference	378
	8.22.1 Detailed Description	378
8.23	number_theory.h File Reference	378
	8.23.1 Detailed Description	380
8.24	operations.h File Reference	380
	8.24.1 Detailed Description	382
8.25	qpp.h File Reference	382
	8.25.1 Detailed Description	384
	8.25.2 Macro Definition Documentation	384
	8.25.2.1 QPP_UNUSED	384
8.26	random.h File Reference	384
	8.26.1 Detailed Description	385
8.27	statistics.h File Reference	386
	8.27.1 Detailed Description	387
8.28	traits.h File Reference	387
	8.28.1 Detailed Description	388
8.29	types.h File Reference	388
	8.29.1 Detailed Description	389
8.30	/Users/vlad/qpp/README.md File Reference	389
Index		391

Chapter 1

Quantum++

Version 1.1 - 26 November 2018

Build status:

Chat (questions/issues)

About

Quantum++ is a modern C++11 general purpose quantum computing library, composed solely of template header files. Quantum++ is written in standard C++11 and has very low external dependencies, using only the Eigen 3 linear algebra header-only template library and, if available, the OpenMP multi-processing library.

Quantum++ is not restricted to qubit systems or specific quantum information processing tasks, being capable of simulating arbitrary quantum processes. The main design factors taken in consideration were the ease of use, high portability, and high performance. The library's simulation capabilities are only restricted by the amount of available physical memory. On a typical machine (Intel i5 8Gb RAM) Quantum++ can successfully simulate the evolution of 25 qubits in a pure state or of 12 qubits in a mixed state reasonably fast.

To report any bugs or ask for additional features/enhancements, please submit an issue with an appropriate label.

If you are interesting in contributing to this project, feel free to contact me. Alternatively, create a custom branch, add your contribution, then finally create a pull request. If I accept the pull request, I will merge your custom branch with the latest development branch. The latter will eventually be merged into a future release version. To contribute, you need to have a solid knowledge of C++ (preferably C++11), including templates and the standard library, a basic knowledge of quantum computing and linear algebra, and working experience with Eigen 3.

For additional Eigen 3 documentation see http://eigen.tuxfamily.org/dox/. For a simple Eigen 3 quick ASCII reference see http://eigen.tuxfamily.org/dox/AsciiQuickReference.txt.

Copyright (c) 2013 - 2019 Vlad Gheorghiu, vgheorgh AT gmail DOT com.

License

Quantum++ is distributed under the MIT license. Please see the LICENSE file for more details.

Installation instructions and further documentation

Please see the installation guide https://github.com/vsoftco/qpp/blob/master/INSTALL.md "`INSTALL.md`" and the comprehensive Wiki for further documentation and detailed examples.

The official API documentation is available in PDF and HTML formats in the doc folder.

2 Quantum++

Chapter 2

Namespace Index

2.1 Namespace List

Here is a list of all namespaces with brief descriptions:

qpp
Quantum++ main namespace
qpp::exception
Quantum++ exception hierarchy namespace
qpp::experimental
Experimental/test functions/classes, do not use or modify
qpp::internal
Internal utility functions, do not use them directly or modify them
qpp::literals

4 Namespace Index

Chapter 3

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

qpp::internal::Display_Impl
qpp::internal::IOManipEigen
std::exception
qpp::exception::Exception
qpp::exception::CustomException
gpp::exception::DimsInvalid
qpp::exception::DimsMismatchCvector
gpp::exception::DimsMismatchMatrix
qpp::exception::DimsMismatchRvector
qpp::exception::DimsMismatchVector
gpp::exception::DimsNotEqual
qpp::exception::Duplicates
gpp::exception::InvalidIterator
qpp::exception::MatrixMismatchSubsys
qpp::exception::MatrixNotCvector
qpp::exception::MatrixNotRvector
qpp::exception::MatrixNotSquare
qpp::exception::MatrixNotSquareNorCvector
qpp::exception::MatrixNotSquareNorRvector
gpp::exception::MatrixNotSquareNorVector
qpp::exception::MatrixNotVector
qpp::exception::NoCodeword
qpp::exception::NotBipartite
app::exception::NotImplemented
app::exception::NotQubitCvector
qpp::exception::NotQubitMatrix
app::exception::NotQubitRvector
app::exception::NotQubitSubsys
app::exception::NotQubitVector
qpp::exception::OutOfRange
qpp::exception::PermInvalid
qpp::exception::PermMismatchDims
qpp::exception::QuditAlreadyMeasured
gpp::exception::SizeMismatch
qpp::exception::SubsysMismatchDims

6 Hierarchical Index

qpp::exception::TypeMismatch	
qpp::exception::UndefinedType	
qpp::exception::Unknown	
qpp::exception::ZeroSize	351
false_type	
qpp::is_complex < T >	
qpp::is_iterable < T, typename >	
qpp::Bit_circuit::Gate_count	
qpp::QCircuitDescription::GateStep	
qpp::IDisplay	
qpp::Dynamic_bitset	
qpp::Bit_circuit	
qpp::internal::IOManipEigen	
qpp::internal::IOManipPointer< PointerType >	
qpp::internal::IOManipRange< InputIterator >	
qpp::QCircuit	
qpp::QCircuitDescription	
qpp::QCircuitDescription::iterator::value_type	
qpp::Timer< T, CLOCK_T >	
qpp::IJSON	
qpp::QCircuit	
qpp::QCircuitDescription	277
is_base_of	
qpp::is_matrix_expression< Derived >	
qpp::QCircuitDescription::iterator	
qpp::make_void < Ts >	
qpp::QCircuitDescription::MeasureStep	
qpp::NoiseBase< T >	
qpp::NoiseBase < NoiseType::StateDependent >	
qpp::QubitAmplitudeDampingNoise	
qpp::QubitPhaseDampingNoise	
${\tt qpp::NoiseBase} < {\tt NoiseType::StateIndependent} > \dots $	239
qpp::QubitBitFlipNoise	303
qpp::QubitBitPhaseFlipNoise	
qpp::QubitDepolarizingNoise	306
qpp::QubitPhaseFlipNoise	309
qpp::QuditDepolarizingNoise	313
qpp::NoiseType	246
$\label{eq:qpp::internal::Singleton} \mbox{qpp::internal::Singleton} < \mbox{T} > \dots $	
qpp::internal::Singleton < const Codes >	319
qpp::Codes	134
qpp::internal::Singleton < const Gates >	319
qpp::Gates	
qpp::internal::Singleton< const Init >	
qpp::Init	
" ·	
qpp::internal::Singleton < const States >	
qpp::States	324
qpp::internal::Singleton< RandomDevices >	319
qpp::RandomDevices	316
qpp::NoiseType::StateDependent	324
qpp::NoiseType::StateIndependent	
true_type	
$\label{eq:qpp:is_complex} \mbox{qpp::is_complex} < \mbox{std::complex} < \mbox{T} >> \ \dots $	208
$qpp::is_iterable < \hspace{0.1cm} T, \hspace{0.1cm} to_void < \hspace{0.1cm} decltype(std::declval < \hspace{0.1cm} T \hspace{0.1cm} > ().begin()), \hspace{0.1cm} decltype(std::declty$	
$> ().end()), \ decltype(*(std::declval < T > ().begin())) >> \ \dots $	210

Chapter 4

Class Index

4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

qpp::Bit_circuit	
Classical reversible circuit simulator	129
qpp::Codes	
Const Singleton class that defines quantum error correcting codes	134
qpp::exception::CustomException	
Custom exception	137
qpp::exception::DimsInvalid	
Invalid dimension(s) exception	140
qpp::exception::DimsMismatchCvector	
Dimension(s) mismatch column vector size exception	142
qpp::exception::DimsMismatchMatrix	
Dimension(s) mismatch matrix size exception	144
qpp::exception::DimsMismatchRvector	
Dimension(s) mismatch row vector size exception	146
qpp::exception::DimsMismatchVector	
Dimension(s) mismatch vector size exception	148
qpp::exception::DimsNotEqual	
Dimensions not equal exception	150
qpp::internal::Display_Impl	152
qpp::exception::Duplicates	
System (e.g. std::vector) has duplicates exception	153
qpp::Dynamic_bitset	
Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std←	
	155
qpp::exception::Exception	
Base class for generating Quantum++ custom exceptions	166
qpp::Bit_circuit::Gate_count	170
qpp::Gates	
Const Singleton class that implements most commonly used gates	172
qpp::QCircuitDescription::GateStep	
One step consisting only of gates/operators in the circuit	185
qpp::IDisplay	
Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream&	& os) cons
188	
qpp::IJSON	
Abstract class (interface) that mandates the definition of very basic JSON serialization support	191

8 Class Index

qpp::Init	
Const Singleton class that performs additional initializations/cleanups	193
qpp::exception::InvalidIterator	
Invalid iterator	195
qpp::internal::IOManipEigen	
qpp::internal::IOManipPointer< PointerType >	
qpp::internal::IOManipRange< InputIterator >	203
qpp::is_complex< T >	
Checks whether the type is a complex type	207
qpp::is_complex< std::complex< T > >	
Checks whether the type is a complex number type, specialization for complex types	208
qpp::is_iterable < T, typename >	
Checks whether T is compatible with an STL-like iterable container \dots	209
$qpp::is_iterable < T, to_void < decltype(std::declval < T > ().begin()), \ decltype(std::declval < T > ().end()), \ d$	ecltype(*(std::declval<
Checks whether T is compatible with an STL-like iterable container, specialization for STL-like	
iterable containers	210
qpp::is_matrix_expression< Derived >	
Checks whether the type is an Eigen matrix expression	211
qpp::QCircuitDescription::iterator	
Quantum circuit description bound-checking (safe) iterator	212
qpp::make_void < Ts >	
Helper for qpp::to_void<> alias template	217
qpp::exception::MatrixMismatchSubsys	
Matrix mismatch subsystems exception	218
qpp::exception::MatrixNotCvector	
Matrix is not a column vector exception	220
qpp::exception::MatrixNotRvector	
Matrix is not a row vector exception	222
qpp::exception::MatrixNotSquare	
Matrix is not square exception	224
qpp::exception::MatrixNotSquareNorCvector	
Matrix is not square nor column vector exception	226
qpp::exception::MatrixNotSquareNorRvector	
Matrix is not square nor row vector exception	228
qpp::exception::MatrixNotSquareNorVector	
Matrix is not square nor vector exception	230
qpp::exception::MatrixNotVector	
Matrix is not a vector exception	232
qpp::QCircuitDescription::MeasureStep	
One step consisting only of measurements in the circuit	234
qpp::exception::NoCodeword	
	237
qpp::NoiseBase< T >	
	239
qpp::NoiseType	
Contains template tags used to specify the noise type	246
qpp::exception::NotBipartite	
Not bi-partite exception	247
qpp::exception::NotImplemented	
Code not yet implemented	249
qpp::exception::NotQubitCvector	
Column vector is not 2 x 1 exception	251
qpp::exception::NotQubitMatrix	
Matrix is not 2 x 2 exception	253
qpp::exception::NotQubitRvector	
Row vector is not 1 x 2 exception	255
qpp::exception::NotQubitSubsys	
Subsystems are not qubits exception	257
·	

4.1 Class List

qpp::exception::NotQubitVector	
Vector is not 2 x 1 nor 1 x 2 exception	259
qpp::exception::OutOfRange	
Argument out of range exception	261
qpp::exception::PermInvalid	
Invalid permutation exception	263
qpp::exception::PermMismatchDims	
Permutation mismatch dimensions exception	265
qpp::QCircuit	
Quantum circuit simulator class	267
qpp::QCircuitDescription	
Quantum circuit description class	277
qpp::QubitAmplitudeDampingNoise	
Qubit amplitude damping noise, as described in Nielsen and Chuang	302
qpp::QubitBitFlipNoise	
Qubit bit flip noise	303
qpp::QubitBitPhaseFlipNoise	
Qubit bit-phase flip (dephasing) noise	305
qpp::QubitDepolarizingNoise	
Qubit depolarizing noise	306
qpp::QubitPhaseDampingNoise	
Qubit phase damping noise, as described in Nielsen and Chuang	308
qpp::QubitPhaseFlipNoise	
Qubit phase flip (dephasing) noise	309
qpp::exception::QuditAlreadyMeasured	
Qudit was already measured exception	311
qpp::QuditDepolarizingNoise	
Qudit depolarizing noise	313
qpp::RandomDevices	
Singleton class that manages the source of randomness in the library	316
qpp::internal::Singleton < T >	
Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously	040
recurring template pattern)	319
qpp::exception::SizeMismatch	000
Size mismatch exception	322
qpp::NoiseType::StateDependent	004
Template tag, used whenever the noise is state-dependent	324
qpp::NoiseType::StateIndependent	004
Template tag, used whenever the noise is state-independent	324
qpp::States Const Singleton class that implements most commonly used states	324
qpp::exception::SubsysMismatchDims	324
Subsystems mismatch dimensions exception	334
qpp::Timer< T, CLOCK T >	334
Chronometer	336
qpp::exception::TypeMismatch	550
Type mismatch exception	341
qpp::exception::UndefinedType	341
Not defined for this type exception	343
qpp::exception::Unknown	U -1 U
Unknown exception	345
qpp::QCircuitDescription::iterator::value_type	347
qpp::exception::ZeroSize	0 11
	351

10 Class Index

Chapter 5

File Index

5.1 File List

Here is a list of all files with brief descriptions:

constar	nts.h	
	Constants	363
entangl	lement.h	
	Entanglement functions	364
entropie	es.h	
	Entropy functions	366
function		
	Generic quantum computing functions	367
input_o	output.h	
	Input/output functions	372
instrum	nents.h	
	Measurement functions	373
numbei	r_theory.h	
	Number theory functions	378
operation	ons.h	
	Quantum operation functions	380
qpp.h		
	Quantum++ main header file, includes all other necessary headers	382
random		
	Randomness-related functions	384
statistic		
	Statistics functions	386
traits.h		
	Type traits	387
types.h		
	Type aliases	388
classes	s/circuits.h	
	Support for qudit quantum circuits	353
classes	s/codes.h	
	Quantum error correcting codes	354
classes	s/exception.h	
	Exceptions	355
classes	s/gates.h	
	Quantum gates	357

12 File Index

classes/idisplay.h	
Display interface via the non-virtual interface (NVI) and very basic JSON serialization support	
interface	358
classes/init.h	
Initialization	358
classes/noise.h	
Noise models	359
classes/random_devices.h	
Random devices	360
classes/reversible.h	
Support for classical reversible circuits	361
classes/states.h	
Quantum states	361
classes/timer.h	
Timing	362
experimental/experimental.h	
Experimental/test functions/classes	367
internal/util.h	
Internal utility functions	376
internal/classes/iomanip.h	
Input/output manipulators	374
internal/classes/singleton.h	
Singleton pattern via CRTP	375
MATLAB/matlab.h	
Input/output interfacing with MATLAB	378

Chapter 6

Namespace Documentation

6.1 qpp Namespace Reference

Quantum++ main namespace.

Namespaces

· exception

Quantum++ exception hierarchy namespace.

· experimental

Experimental/test functions/classes, do not use or modify.

internal

Internal utility functions, do not use them directly or modify them.

literals

Classes

· class Bit_circuit

Classical reversible circuit simulator.

• class Codes

const Singleton class that defines quantum error correcting codes

· class Dynamic_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

· class Gates

const Singleton class that implements most commonly used gates

class IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

class IJSON

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

class Init

const Singleton class that performs additional initializations/cleanups

· struct is complex

Checks whether the type is a complex type.

• struct is_complex< std::complex< T > >

Checks whether the type is a complex number type, specialization for complex types.

· struct is_iterable

Checks whether T is compatible with an STL-like iterable container.

 $\bullet \ \ struct\ is_iterable < T,\ to_void < \ decltype(std::declval < T>().begin()),\ decltype(std::declval < T>().end()),\ decltype(*(std::declval < T>().end())),\ decltype(*(std::declval < T>().end()$

Checks whether T is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

• struct is_matrix_expression

Checks whether the type is an Eigen matrix expression.

· struct make void

Helper for qpp::to_void<> alias template.

class NoiseBase

Base class for all noise models, derive your particular noise model.

class NoiseType

Contains template tags used to specify the noise type.

class QCircuit

Quantum circuit simulator class.

· class QCircuitDescription

Quantum circuit description class.

· class QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

class QubitBitFlipNoise

Qubit bit flip noise.

• class QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

· class QubitDepolarizingNoise

Qubit depolarizing noise.

· class QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

class QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

· class QuditDepolarizingNoise

Qudit depolarizing noise.

· class RandomDevices

Singleton class that manages the source of randomness in the library.

· class States

const Singleton class that implements most commonly used states

· class Timer

Chronometer.

Typedefs

```
• template<typename... Ts>
```

```
using to_void = typename make_void < Ts... >::type
```

Alias template that implements the proposal for void_t.

• using idx = std::size t

Non-negative integer index, make sure you use an unsigned type.

• using bigint = long long int

Big integer.

using cplx = std::complex< double >

Complex number in double precision.

• using ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector. using bra = Eigen::RowVectorXcd Complex (double precision) dynamic Eigen row vector. • using cmat = Eigen::MatrixXcd Complex (double precision) dynamic Eigen matrix. using dmat = Eigen::MatrixXd Real (double precision) dynamic Eigen matrix. template<typename Scalar > using dyn mat = Eigen::Matrix < Scalar, Eigen::Dynamic, Eigen::Dynamic > Dynamic Eigen matrix over the field specified by Scalar. • template<typename Scalar > using dyn_col_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 > Dynamic Eigen column vector over the field specified by Scalar. template<typename Scalar > using dyn_row_vect = Eigen::Matrix < Scalar, 1, Eigen::Dynamic > Dynamic Eigen row vector over the field specified by Scalar. **Functions** • constexpr cplx operator"" _i (long double x) noexcept User-defined literal for complex $i = \sqrt{-1}$ (real overload) cplx omega (idx D) D-th root of unity. • template<typename Derived > dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt coefficients of the bi-partite pure state A. template<typename Derived > dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2) Schmidt coefficients of the bi-partite pure state A. template<typename Derived > cmat schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt basis on Alice side. • template<typename Derived > cmat schmidtA (const Eigen::MatrixBase< Derived > &A, idx d=2) Schmidt basis on Alice side. template<typename Derived > cmat schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt basis on Bob side. template<typename Derived > cmat schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2) Schmidt basis on Bob side. template<typename Derived > std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt probabilities of the bi-partite pure state A.

std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)

double entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)

template<typename Derived >

template<typename Derived >

Schmidt probabilities of the bi-partite pure state A.

Entanglement of the bi-partite pure state A.

```
• template<typename Derived >
  double entanglement (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Entanglement of the bi-partite pure state A.

    template<typename Derived >

  double gconcurrence (const Eigen::MatrixBase< Derived > &A)
     G-concurrence of the bi-partite pure state A.

    template<typename Derived >

  double negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Negativity of the bi-partite mixed state A.

    template < typename Derived >

  double negativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Negativity of the bi-partite mixed state A.

    template < typename Derived >

  double lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Logarithmic negativity of the bi-partite mixed state A.
• template<typename Derived >
  double lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Logarithmic negativity of the bi-partite mixed state A.
• template<typename Derived >
  double concurrence (const Eigen::MatrixBase< Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.
• template<typename Derived >
  double entropy (const Eigen::MatrixBase< Derived > &A)
      von-Neumann entropy of the density matrix A

    double entropy (const std::vector< double > &prob)

     Shannon entropy of the probability distribution prob.

    template<typename Derived >

  double renyi (const Eigen::MatrixBase< Derived > &A, double alpha)
      Renyi- \alpha entropy of the density matrix A, for \alpha \geq 0.

    double renyi (const std::vector< double > &prob, double alpha)

     Renyi- \alpha entropy of the probability distribution prob, for \alpha > 0.

    template<typename Derived >

  double tsallis (const Eigen::MatrixBase< Derived > &A, double q)
      Tsallis- q entropy of the density matrix A, for q > 0.

    double tsallis (const std::vector< double > &prob, double q)

      Tsallis- q entropy of the probability distribution prob, for q > 0.
• template<typename Derived >
  double qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx > &subsysB, const std::vector< idx > &dims)
     Quantum mutual information between 2 subsystems of a composite system.

    template<typename Derived >

  double gmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx> &subsysB, idx d=2)
      Quantum mutual information between 2 subsystems of a composite system.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > transpose (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > adjoint (const Eigen::MatrixBase< Derived > &A)
     Adjoint.
```

```
    template<typename Derived >

  dyn_mat< typename Derived::Scalar > inverse (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  Derived::Scalar trace (const Eigen::MatrixBase< Derived > &A)
      Trace
• template<typename Derived >
  Derived::Scalar det (const Eigen::MatrixBase< Derived > &A)
     Determinant.

    template<typename Derived >

  Derived::Scalar logdet (const Eigen::MatrixBase< Derived > &A)
     Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar sum (const Eigen::MatrixBase< Derived > &A)
      Element-wise sum of A.
• template<typename Derived >
  Derived::Scalar prod (const Eigen::MatrixBase< Derived > &A)
     Element-wise product of A.

    template<typename Derived >

  double norm (const Eigen::MatrixBase< Derived > &A)
     Frobenius norm.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > normalize (const Eigen::MatrixBase< Derived > &A)
     Normalizes state vector (column or row vector) or density matrix.

    template<typename Derived >

  std::pair < dyn_col_vect < cplx >, cmat > eig (const Eigen::MatrixBase < Derived > &A)
     Full eigen decomposition.

    template<typename Derived >

  dyn_col_vect< cplx > evals (const Eigen::MatrixBase< Derived > &A)
     Eigenvalues.

    template<typename Derived >

  cmat evects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors.

    template<typename Derived >

  std::pair< dyn_col_vect< double >, cmat > heig (const Eigen::MatrixBase< Derived > &A)
     Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > hevals (const Eigen::MatrixBase< Derived > &A)
     Hermitian eigenvalues.
• template<typename Derived >
  cmat hevects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors of Hermitian matrix.
• template<typename Derived >
  std::tuple< cmat, dyn_col_vect< double >, cmat > svd (const Eigen::MatrixBase< Derived > &A)
     Full singular value decomposition.

    template<typename Derived >

  dyn_col_vect< double > svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.
• template<typename Derived >
  cmat svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.

    template<typename Derived >

  cmat svdV (const Eigen::MatrixBase< Derived > &A)
```

Direct sum.

```
Right singular vectors.
• template<typename Derived >
  cmat funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)

    template<typename Derived >

  cmat sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.

    template<typename Derived >

  cmat absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.

    template<typename Derived >

  cmat expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.

    template<typename Derived >

  cmat logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.
• template<typename Derived >
  cmat sinm (const Eigen::MatrixBase< Derived > &A)
     Matrix sin.

    template<typename Derived >

  cmat cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.
template<typename Derived >
  cmat spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.
• template<typename Derived >
  \label{eq:const_equation} \mbox{dyn\_mat} < \mbox{typename Derived::Scalar} > \mbox{powm (const Eigen::MatrixBase} < \mbox{Derived} > \&\mbox{A, idx n)}
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.
• template<typename Derived >
  double schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const type-
  name Derived::Scalar &))
     Functor.
template<typename T >
  dyn_mat< typename T::Scalar > kron (const T &head)
     Kronecker product.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > kron (const T &head, const Args &... tail)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > kron (const std::vector< Derived > &As)
     Kronecker product.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > kron (const std::initializer_list< Derived > &As)
     Kronecker product.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Kronecker power.

    template<typename T >

  dyn_mat< typename T::Scalar > dirsum (const T &head)
```

```
• template<typename T, typename... Args>
  dyn_mat< typename T::Scalar > dirsum (const T &head, const Args &... tail)
     Direct sum.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > dirsum (const std::vector< Derived > &As)

    template<typename Derived >

  dyn mat< typename Derived::Scalar > dirsum (const std::initializer list< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > reshape (const Eigen::MatrixBase< Derived > &A, idx rows, idx
  cols)
     Reshape.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > comm (const Eigen::MatrixBase< Derived1 > &A, const Eigen::⊷
  MatrixBase< Derived2 > &B)
     Commutator.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > prj (const Eigen::MatrixBase< Derived > &A)
     Projector.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > grams (const std::vector< Derived > &As)
     Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > grams (const std::initializer_list< Derived > &As)
      Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > grams (const Eigen::MatrixBase< Derived > &A)
     Gram-Schmidt orthogonalization.

    std::vector< idx > n2multiidx (idx n, const std::vector< idx > &dims)

     Non-negative integer index to multi-index.

    idx multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

     Multi-index to non-negative integer index.

    ket mket (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Multi-partite qudit ket.

    ket mket (const std::vector< idx > &mask, idx d=2)

     Multi-partite qudit ket.

    cmat mprj (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Projector onto multi-partite qudit ket.

    cmat mprj (const std::vector < idx > &mask, idx d=2)

     Projector onto multi-partite qudit ket.
• template<typename InputIterator >
  std::vector< double > abssq (InputIterator first, InputIterator last)
```

Computes the absolute values squared of an STL-like range of complex numbers.

• template<typename Container >

std::vector< double > abssq (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Computes the absolute values squared of an STL-like container.

template<typename Derived >

```
std::vector< double > abssq (const Eigen::MatrixBase< Derived > &A)
```

Computes the absolute values squared of an Eigen expression.

template<typename InputIterator >

std::iterator_traits< InputIterator >::value_type sum (InputIterator first, InputIterator last)

Element-wise sum of an STL-like range.

• template<typename Container >

Container::value_type sum (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

std::iterator traits < InputIterator >::value type prod (InputIterator first, InputIterator last)

Element-wise product of an STL-like range.

• template<typename Container >

Container::value_type prod (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Element-wise product of the elements of an STL-like container.

template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > rho2pure (const Eigen::MatrixBase< Derived > &A)
```

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

std::vector< idx > complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

• template<typename Derived >

```
std::vector< double > rho2bloch (const Eigen::MatrixBase< Derived > &A)
```

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

• template<typename Derived >

internal::IOManipEigen disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)

Eigen expression ostream manipulator.

internal::IOManipEigen disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

• template<typename InputIterator >

internal::IOManipRange < InputIterator > disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")

Range ostream manipulator.

 $\bullet \ \ \text{template}{<} \text{typename Container} >$

internal::IOManipRange< typename Container::const_iterator > disp (const Container &c, const std::string &separator, const std::string &start="[", const std::string &end="]", typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

template<typename PointerType >

internal::IOManipPointer< PointerType > disp (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")

C-style pointer ostream manipulator.

template<typename Derived >

```
void save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)
```

Saves Eigen expression to a binary file (internal format) in double precision.

template<typename Derived >

dyn_mat< typename Derived::Scalar > load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.

• template<typename Derived >

 $\label{lem:dyn_col_vect} $$ \displaystyle \operatorname{dyn_col_vect} < \operatorname{typename \ Derived}::Scalar > ip (const \ Eigen::MatrixBase < \operatorname{Derived} > & phi, const \ Eigen:: \longleftrightarrow \\ \operatorname{MatrixBase} < \operatorname{Derived} > & psi, const \ std::vector < idx > & subsys, const \ std::vector < idx > & dims) \\ $$ \displaystyle \operatorname{dyn_col_vect} < \operatorname{dyn_col_v$

Generalized inner product.

• template<typename Derived >

dyn_col_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template<typename Derived >

 $std::tuple < std::vector < idx >, \ double, \ cmat > measure_seq \ (const \ Eigen::MatrixBase < Derived > \&A, \\ std::vector < idx > target, \ idx \ d=2)$

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

ullet template<typename Derived >

 $std::enable_if < std::is_same < typename Derived::Scalar, cplx >::value, dyn_mat < cplx > ::type \\ loadMATLAB (const std::string &mat_file, const std::string &var_name)$

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::

Scalar > >::type loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

std::vector< int > x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

bigint gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > invperm (const std::vector< idx > &perm)

Inverse permutation.

• std::vector< idx > compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

std::vector< bigint > factors (bigint a)

Prime factor decomposition.

• bigint modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

bigint modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple < bigint, bigint, bigint > egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint modinv (bigint a, bigint p)

Modular inverse of a mod p.

bool isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

bigint randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

std::vector< std::pair< int, int > > convergents (const std::vector< int > &cf)

Convergents

std::vector< std::pair< int, int > > convergents (double x, idx N)

Convergents.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, const
std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

- template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, idx
d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)
```

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

template<typename Derived >

cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, const std::vector< idx > &dims)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

• template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, idx d=2)
```

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat kraus2super (const std::vector < cmat > &Ks)

Superoperator matrix.

cmat kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector< cmat > choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

template<typename Derived >

```
\label{lem:dyn_mat}  \mbox{dyn\_mat} < \mbox{typename Derived::Scalar} > \mbox{ptrace1} \mbox{ (const Eigen::MatrixBase} < \mbox{Derived} > \&\mbox{A, const std} \\ \mbox{::vector} < \mbox{idx} > \&\mbox{dims})
```

Partial trace.

 $\bullet \ \ {\sf template}{<} {\sf typename \ Derived} >$

```
dyn_mat< typename Derived::Scalar > ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.
```

template<typename Derived >

```
\frac{dyn\_mat<}{typename} \ Derived::Scalar > ptrace2 \ (const \ Eigen::MatrixBase< \ Derived > \&A, \ const \ std \\ \because vector < idx > \&dims)
```

Partial trace.

• template<typename Derived >

```
dyn_mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)
```

Partial trace.

ullet template<typename Derived >

 $\frac{dyn_mat}{dx}$ typename Derived::Scalar > $\frac{dyn_mat}{dx}$ (const Eigen::MatrixBase < Derived > &A, const std::vector < $\frac{dx}{dx}$ > &target, const std::vector < $\frac{dx}{dx}$ > &dims)

Partial trace.

ullet template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector
idx > &target, idx d=2)

Partial trace.

template<typename Derived >

Partial transpose.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptranspose (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial transpose.

• template<typename Derived >

Subsystem permutation.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > syspermute (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &perm, idx d=2)

Subsystem permutation.

template<typename Derived >

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_mat< typename Derived::Scalar > applyTFQ (const Eigen::MatrixBase< Derived > &A, const std↔ ::vector< idx > &target, idx d=2, bool swap=true)

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool
swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool
swap=true)

Qudit quantum Fourier transform.

• double rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

• bigint rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx randidx (idx a=std::numeric_limits < idx >::min(), idx b=std::numeric_limits < idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

Derived rand (idx rows, idx cols, double a=0, double b=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

• template<>

dmat rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (gpp::dmat)

• template<>

cmat rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived randn (idx rows, idx cols, double mean=0, double sigma=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

dmat randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

template<>

cmat randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

• double randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

• cmat randU (idx D=2)

Generates a random unitary matrix.

· cmat randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat randH (idx D=2)

Generates a random Hermitian matrix.

• ket randket (idx D=2)

Generates a random normalized ket (pure state vector)

cmat randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.

std::vector< double > uniform (idx N)

Uniform probability distribution vector.

std::vector< double > marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > marginalY (const dmat &probXY)

Marginal distribution.

 $\bullet \ \ \text{template}{<} \text{typename Container} >$

double avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable<
Container >::value >::type *=nullptr)

Average.

• template<typename Container >

double cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is iterable< Container >::value >::type *=nullptr)

Covariance.

• template<typename Container >

double var (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable<
Container >::value >::type *=nullptr)

Variance.

template<typename Container >
 double sigma (const std::vector< double > &prob, const Container &X, typename std::enable_if<
 is_iterable< Container >::value >::type *=nullptr)

Standard deviation.

• template<typename Container >

double cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Correlation.

Variables

• constexpr double chop = 1e-10

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

constexpr double eps = std::numeric_limits<double>::epsilon()

Used to decide whether a number or expression in double precision is zero or not for the purpose of a specific computation.

• constexpr idx maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

constexpr double pi = 3.141592653589793238462643383279502884

 π

constexpr double ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

constexpr double infty = std::numeric_limits<double>::max()

Used to denote infinity in double precision.

const idx idx infty = static cast<idx>(-1)

Used to denote the largest unsigned index.

6.1.1 Detailed Description

Quantum++ main namespace.

6.1.2 Typedef Documentation

6.1.2.1 bigint

```
using qpp::bigint = typedef long long int
```

Big integer.

6.1.2.2 bra

```
using qpp::bra = typedef Eigen::RowVectorXcd
```

Complex (double precision) dynamic Eigen row vector.

```
6.1.2.3 cmat
```

```
using qpp::cmat = typedef Eigen::MatrixXcd
```

Complex (double precision) dynamic Eigen matrix.

6.1.2.4 cplx

```
using qpp::cplx = typedef std::complex<double>
```

Complex number in double precision.

6.1.2.5 dmat

```
using qpp::dmat = typedef Eigen::MatrixXd
```

Real (double precision) dynamic Eigen matrix.

6.1.2.6 dyn_col_vect

```
template<typename Scalar >
using qpp::dyn_col_vect = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, 1>
```

Dynamic Eigen column vector over the field specified by Scalar.

Example:

```
// type of colvect is Eigen::Matrix<float, Eigen::Dynamic, 1>
dyn_col_vect<float> colvect(2);
```

6.1.2.7 dyn_mat

```
template<typename Scalar >
using qpp::dyn_mat = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, Eigen::Dynamic>
```

Dynamic Eigen matrix over the field specified by Scalar.

Example:

```
// type of mat is Eigen::Matrix<float, Eigen::Dynamic, Eigen::Dynamic>
dyn_mat<float> mat(2, 3);
```

```
6.1.2.8 dyn_row_vect
```

```
template<typename Scalar >
using qpp::dyn_row_vect = typedef Eigen::Matrix<Scalar, 1, Eigen::Dynamic>
```

Dynamic Eigen row vector over the field specified by Scalar.

Example:

```
// type of rowvect is Eigen::Matrix<float, 1, Eigen::Dynamic>
dyn_row_vect<float> rowvect(3);
```

6.1.2.9 idx

```
using qpp::idx = typedef std::size_t
```

Non-negative integer index, make sure you use an unsigned type.

6.1.2.10 ket

```
using qpp::ket = typedef Eigen::VectorXcd
```

Complex (double precision) dynamic Eigen column vector.

6.1.2.11 to_void

```
template<typename... Ts>
using qpp::to_void = typedef typename make_void<Ts...>::type
```

Alias template that implements the proposal for void_t.

See also

```
http://www.open-std.org/jtc1/sc22/wg21/docs/papers/2014/n3911
```

6.1.3 Function Documentation

6.1.3.1 absm()

Matrix absolute value.

Parameters

```
A Eigen expression
```

Returns

Matrix absolute value of A

Computes the absolute values squared of an STL-like range of complex numbers.

Parameters

	Iterator to the first element of the range
last	Iterator to the last element of the range

InputIterator last)

Returns

Real vector consisting of the range absolute values squared

```
6.1.3.3 abssq() [2/3]
```

Computes the absolute values squared of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Real vector consisting of the container's absolute values squared

Computes the absolute values squared of an Eigen expression.

Parameters

```
A Eigen expression
```

Returns

Real vector consisting of the absolute values squared

6.1.3.5 adjoint()

Adjoint.

Parameters

```
A Eigen expression
```

Returns

Adjoint (Hermitian conjugate) of A, as a dynamic matrix over the same scalar field as A

6.1.3.6 anticomm()

Anti-commutator.

See also

qpp::comm()

Anti-commutator $\{A,B\} = AB + BA$. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
В	Eigen expression

Returns

Anti-commutator AB + BA, as a dynamic matrix over the same scalar field as A

6.1.3.7 apply() [1/5]

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

Returns

Gate A applied to the part target of state

6.1.3.8 apply() [2/5]

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

Returns

Gate A applied to the part target of state

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes where the Kraus operators Ks are applied
dims	Dimensions of the multi-partite system

Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes where the Kraus operators Ks are applied
d	Subsystem dimensions

Returns

Output density matrix after the action of the channel

6.1.3.12 applyCTRL() [1/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate *A* must match the dimension of *target*. Also, all control subsystems in *ctrl* must have the same dimension.

Parameters

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

Returns

CTRL-A gate applied to the part target of state

6.1.3.13 applyCTRL() [2/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

Returns

CTRL-A gate applied to the part target of state

6.1.3.14 applyQFT()

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

Parameters

Α	Eigen expression
target	Subsystem indexes where the QFT is applied
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Qudit Quantum Fourier transform applied to the part target of A

6.1.3.15 applyTFQ()

Applies the inverse (adjoint) qudit quantum Fourier transform to the part *target* of the multi-partite state vector or density matrix *A*.

Parameters

Α	Eigen expression
target	Subsystem indexes where the TFQ is applied
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Inverse (adjoint) qudit Quantum Fourier transform applied to the part target of A

6.1.3.16 avg()

Average.

Parameters

prob	Real probability vector representing the probability distribution of X
Χ	Real random variable values represented by an STL-like container

Returns

Average of X

6.1.3.17 bloch2rho()

Computes the density matrix corresponding to the 3-dimensional real Bloch vector *r*.

See also

qpp::rho2bloch()

Parameters

r 3-dimensional real vector

Returns

Qubit density matrix

6.1.3.18 choi2kraus()

Orthogonal Kraus operators from Choi matrix.

See also

qpp::kraus2choi()

Extracts a set of orthogonal (under Hilbert-Schmidt operator norm) Kraus operators from the Choi matrix A

Note

The Kraus operators satisfy $Tr(K_i^{\dagger}K_j)=\delta_{ij}$ for all $i\neq j$

Parameters



Returns

Set of orthogonal Kraus operators


6.1.3.19 choi2super()

Converts Choi matrix to superoperator matrix.

See also

qpp::super2choi()

Parameters



Returns

Superoperator matrix

6.1.3.20 comm()

Commutator.

See also

qpp::anticomm()

Commutator [A, B] = AB - BA. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
В	Eigen expression

Returns

Commutator AB - BA, as a dynamic matrix over the same scalar field as A

6.1.3.21 complement()

Constructs the complement of a subsystem vector.

Parameters

subsys	Subsystem vector
n	Total number of systems

Returns

Complement of *subsys* with respect to the set $\{0, 1, \dots, n-1\}$

6.1.3.22 compperm()

Compose permutations.

Parameters

perm	Permutation
sigma	Permutation

Returns

Composition of the permutations *perm* o *sigma* = perm(sigma)

6.1.3.23 concurrence()

Wootters concurrence of the bi-partite qubit mixed state A.

Parameters

```
A Eigen expression
```

Returns

Wootters concurrence

6.1.3.24 conjugate()

Complex conjugate.

Parameters

```
A Eigen expression
```

Returns

Complex conjugate of A, as a dynamic matrix over the same scalar field as A

6.1.3.25 contfrac2x()

Real representation of a simple continued fraction.

See also

```
qpp::x2contfrac()
```

Note

If N is greater than the size of cf (by default it is), then all terms in cf are considered.

Parameters

	Integer vector containing the simple continued fraction expansion
Ν	Number of terms considered in the continued fraction expansion.

Returns

Real representation of the simple continued fraction

6.1.3.26 convergents() [1/2]

```
std::vector<std::pair<int, int> > qpp::convergents ( const std::vector< int > & cf ) [inline]
```

Convergents.

See also

```
qpp::contfrac2x() and qpp::x2contfrac()
```

Parameters

```
cf Continued fraction
```

Returns

Vector of convergents pairs (a_k, b_k) that approximate the number represented by the continued fraction

6.1.3.27 convergents() [2/2]

```
std::vector<std::pair<int, int> > qpp::convergents ( double x, idx N) [inline]
```

Convergents.

See also

```
qpp::contfrac2x() and qpp::x2contfrac()
```

Note

In the continued fraction expansion of x has less terms than N, then the series of convergents is truncated to the number of terms in the continued fraction expansion of x.

Parameters

Х	Real number
Ν	Number of convergents.

Returns

Vector of convergents pairs (a_k,b_k) that approximate the number \emph{x}

6.1.3.28 cor()

Correlation.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels the rows, Y labels the columns)
X	Real random variable values represented by an STL-like container
Y	Real random variable values represented by an STL-like container

Returns

Correlation of X and Y

6.1.3.29 cosm()

Matrix cos.

Parameters

```
A Eigen expression
```

Returns

Matrix cosine of A

6.1.3.30 cov()

Covariance.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels the rows, Y labels the columns)
Χ	Real random variable values represented by an STL-like container
Y	Real random variable values represented by an STL-like container

Returns

Covariance of X and Y

6.1.3.31 cwise()

Functor.

Parameters

Α	Eigen expression
f	Pointer-to-function from scalars of A to OutputScalar

Returns

Component-wise f(A), as a dynamic matrix over the *OutputScalar* scalar field

6.1.3.32 det()

Determinant.

Parameters

A Eigen expression

Returns

Determinant of A, as a scalar over the same scalar field as A. Returns $\pm \infty$ when the determinant overflows/underflows.

```
6.1.3.33 dirsum() [1/4]
```

Direct sum.

See also

qpp::dirsumpow()

Used to stop the recursion for the variadic template version of qpp::dirsum()

Parameters

head	Eigen expression
ncau	Ligon capicosion

Its argument head

Direct sum.

See also

qpp::dirsumpow()

Parameters

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

Returns

Direct sum of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

```
6.1.3.35 dirsum() [3/4]
```

Direct sum.

See also

qpp::dirsumpow()

Parameters

As std::vector of Eigen expressions

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Direct sum.

See also

qpp::dirsumpow()

Parameters

As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}

Returns

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.3.37 dirsumpow()

Direct sum power.

See also

qpp::dirsum()

Parameters

Α	Eigen expression
n	Non-negative integer

Direct sum of A with itself n times $A^{\oplus n}$, as a dynamic matrix over the same scalar field as A

Eigen expression ostream manipulator.

Parameters

Α	Eigen expression
chop	Set to zero the elements smaller in absolute value than <i>chop</i>

Returns

Instance of qpp::internal::IOManipEigen

Complex number ostream manipulator.

Parameters

Z	Complex number (or any other type implicitly cast-able to std::complex <double>)</double>
chop	Set to zero the elements smaller in absolute value than chop

Returns

Instance of qpp::internal::IOManipEigen

```
6.1.3.40 disp() [3/5]

template<typename InputIterator >
internal::IOManipRange<InputIterator> qpp::disp (
```

```
InputIterator first,
InputIterator last,
const std::string & separator,
const std::string & start = "[",
const std::string & end = "]")
```

Range ostream manipulator.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipRange

```
6.1.3.41 disp() [4/5]
```

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

Parameters

С	Container
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipRange

6.1.3.42 disp() [5/5]

```
template<typename PointerType >
internal::IOManipPointer<PointerType> qpp::disp (
```

```
const PointerType * p,
idx N,
const std::string & separator,
const std::string & start = "[",
const std::string & end = "]")
```

C-style pointer ostream manipulator.

Parameters

р	Pointer to the first element
N	Number of elements to be displayed
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipPointer

6.1.3.43 egcd()

Extended greatest common divisor of two integers.

See also

qpp::gcd()

Parameters

а	Integer
b	Integer

Returns

Tuple of: 1. Integer m, 2. Integer n, and 3. Non-negative integer gcd(a,b) such that ma + nb = gcd(a,b)

6.1.3.44 eig()

Full eigen decomposition.

See also

qpp::heig()

Parameters

```
A Eigen expression
```

Returns

Pair of: 1. Eigenvalues of *A*, as a complex dynamic column vector, and 2. Eigenvectors of *A*, as columns of a complex dynamic matrix

6.1.3.45 entanglement() [1/2]

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

```
qpp::entropy()
```

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Entanglement, with the logarithm in base 2

6.1.3.46 entanglement() [2/2]

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

qpp::entropy()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Entanglement, with the logarithm in base 2

6.1.3.47 entropy() [1/2]

von-Neumann entropy of the density matrix A

Parameters

```
A Eigen expression
```

Returns

von-Neumann entropy, with the logarithm in base 2

6.1.3.48 entropy() [2/2]

Shannon entropy of the probability distribution prob.

Parameters

prob Real probability vector

Returns

Shannon entropy, with the logarithm in base 2

```
6.1.3.49 evals()
```

Eigenvalues.

See also

qpp::hevals()

Parameters

```
A Eigen expression
```

Returns

Eigenvalues of A, as a complex dynamic column vector

6.1.3.50 evects()

Eigenvectors.

See also

qpp::hevects()

Parameters

```
A Eigen expression
```

Returns

Eigenvectors of A, as columns of a complex dynamic matrix

6.1.3.51 expm()

Matrix exponential.

Parameters

A Eigen expression

Returns

Matrix exponential of A

6.1.3.52 factors()

Prime factor decomposition.

Note

Runs in $\mathcal{O}(\sqrt{n})$ time complexity

Parameters

a Integer different from 0, 1 or -1

Returns

Integer vector containing the factors

6.1.3.53 funm()

Functional calculus f(A)

Parameters

Α	Eigen expression
f	Pointer-to-function from complex to complex

```
Returns
```

```
f(A)
```

Greatest common divisor of two integers.

See also

```
qpp::lcm()
```

Parameters

а	Integer
b	Integer

Returns

Greatest common divisor of a and b

Greatest common divisor of a list of integers.

See also

```
qpp::lcm()
```

Parameters

```
as List of integers
```

Returns

Greatest common divisor of all numbers in as

6.1.3.56 gconcurrence()

G-concurrence of the bi-partite pure state A.

Note


Both local dimensions must be equal

Uses qpp::logdet() to avoid overflows

See also

qpp::logdet()

Parameters



Returns

G-concurrence

```
6.1.3.57 grams() [1/3]
```

Gram-Schmidt orthogonalization.

Parameters

```
As std::vector of Eigen expressions as column vectors
```

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

```
6.1.3.58 grams() [2/3]
```

Gram-Schmidt orthogonalization.

Parameters

```
As std::initializer_list of Eigen expressions as column vectors
```

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

Gram-Schmidt orthogonalization.

Parameters

A Eigen expression, the input vectors are the columns of A

Returns

Gram-Schmidt vectors of the columns of A, as columns of a dynamic matrix over the same scalar field as A

6.1.3.60 heig()

Full eigen decomposition of Hermitian expression.

See also

qpp::eig()

Parameters

A Eigen expression

Pair of: 1. Eigenvalues of A, as a real dynamic column vector, and 2. Eigenvectors of A, as columns of a complex dynamic matrix

6.1.3.61 hevals()

Hermitian eigenvalues.

See also

qpp::evals()

Parameters

A Eigen expression

Returns

Eigenvalues of Hermitian A, as a real dynamic column vector

6.1.3.62 hevects()

Eigenvectors of Hermitian matrix.

See also

qpp::evects()

Parameters

A Eigen expression

Returns

Eigenvectors of Hermitian matrix A, as columns of a complex matrix

6.1.3.63 inverse()

Inverse.

Parameters

```
A Eigen expression
```

Returns

Inverse of A, as a dynamic matrix over the same scalar field as A

6.1.3.64 invperm()

```
\label{eq:std:vector} $$ std::vector < idx > & perm ) $$ [inline] $$
```

Inverse permutation.

Parameters

perm Permut	ation
-------------	-------

Returns

Inverse of the permutation perm

6.1.3.65 ip() [1/2]

Generalized inner product.

Parameters

phi	hi Column vector Eigen expression	
psi	Column vector Eigen expression	
subsys	Subsystem indexes over which phi is defined	
dims	Dimensions of the multi-partite system	

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

Generalized inner product.

Parameters

phi	Column vector Eigen expression
psi	Column vector Eigen expression
subsys	Subsystem indexes over which phi is defined
d	Subsystem dimensions

Returns

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

6.1.3.67 isprime()

Primality test based on the Miller-Rabin's algorithm.

Parameters

p	Integer different from 0, 1 or -1
k	Number of iterations. The probability of a false positive is 2^{-k} .

Returns

True if the number is (most-likely) prime, false otherwise

6.1.3.68 kraus2choi()

Choi matrix.

See also

qpp::choi2kraus()

Constructs the Choi matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|, |0\rangle\langle 1|$ etc.

Note

The superoperator matrix S and the Choi matrix C are related by $S_{ab,mn}=C_{ma,nb}$

Parameters

Ks Set of Kraus operators

Returns

Choi matrix

6.1.3.69 kraus2super()

Superoperator matrix.

Constructs the superoperator matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|$, $|0\rangle\langle 1|$ etc.

Parameters

Ks Set of Kraus operators

Returns

Superoperator matrix

Kronecker product.

See also

qpp::kronpow()

Used to stop the recursion for the variadic template version of app::kron()

Parameters

head	Eigen expression
------	------------------

Returns

Its argument head

```
6.1.3.71 kron() [2/4]
```

Kronecker product.

See also

qpp::kronpow()

Parameters

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

Returns

Kronecker product of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

See also

qpp::kronpow()

Parameters

As std::vector of Eigen expressions

Returns

Kronecker product of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Kronecker product.

See also

qpp::kronpow()

Parameters

As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}

Returns

Kronecker product of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.3.74 kronpow()

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::kronpow (
```

```
const Eigen::MatrixBase< Derived > & A, idx n)
```

Kronecker power.

See also

qpp::kron()

Parameters

Α	Eigen expression
n	Non-negative integer

Returns

Kronecker product of A with itself n times $A^{\otimes n}$, as a dynamic matrix over the same scalar field as A

Least common multiple of two integers.

See also

qpp::gcd()

Parameters

а	Integer
b	Integer

Returns

Least common multiple of a and b

Least common multiple of a list of integers.

See also

```
qpp::gcd()
```

Parameters

```
as List of integers
```

Returns

Least common multiple of all numbers in as

6.1.3.77 load()

Loads Eigen matrix from a binary file (internal format) in double precision.

See also

```
qpp::save()
```

The template parameter cannot be automatically deduced and must be explicitly provided, depending on the scalar field of the matrix that is being loaded.

Example:

```
// loads a previously saved Eigen dynamic complex matrix from "input.bin" cmat mat = load<cmat>("input.bin");
```

Parameters

```
fname Output file name
```

6.1.3.78 loadMATLAB() [1/2]

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

```
qpp::saveMATLAB()
```

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen ket
// from the MATLAB file "input.mat"
ket psi = loadMATLABket>("input.mat");
```

Template Parameters

Derived	Complex Eigen type
---------	--------------------

Parameters

mat_file	MATALB .mat file	
var_name	Variable name in the .mat file representing the matrix to be loaded]

Returns

Eigen dynamic matrix

6.1.3.79 loadMATLAB() [2/2]

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

```
qpp::saveMATLAB()
```

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen dynamic double matrix
// from the MATLAB file "input.mat"
dmat mat = loadMATLAB<dmat>("input.mat");
```

Template Parameters

е
е

Parameters

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be loaded

Returns

Eigen dynamic matrix

6.1.3.80 logdet()

Logarithm of the determinant.

Useful when the determinant overflows/underflows

Parameters

```
A Eigen expression
```

Returns

Logarithm of the determinant of A, as a scalar over the same scalar field as A

6.1.3.81 logm()

Matrix logarithm.

Parameters

A Eigen expression

Matrix logarithm of A

Logarithmic negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Logarithmic negativity, with the logarithm in base 2

6.1.3.83 lognegativity() [2/2]

```
template<typename Derived >
double qpp::lognegativity (
          const Eigen::MatrixBase< Derived > & A,
          idx d = 2 )
```

Logarithmic negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Logarithmic negativity, with the logarithm in base 2

6.1.3.84 marginalX()

Marginal distribution.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels	1
	the rows, Y labels the columns)	

Returns

Real vector consisting of the marginal distribution of X

6.1.3.85 marginalY()

Marginal distribution.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels	
	the rows, Y labels the columns)	

Returns

Real vector consisting of the marginal distribution of Y

6.1.3.86 measure() [1/9]

Measures the state vector or density operator A using the set of Kraus operators Ks.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.87 measure() [2/9]

Measures the state vector or density matrix A using the set of Kraus operators Ks.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.88 measure() [3/9]

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

Parameters

Α	Eigen expression	
U	Unitary matrix whose columns represent the measurement basis vectors	

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.89 measure() [4/9]

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.90 measure() [5/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.92 measure() [7/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.93 measure() [8/9]

Measures the part *target* of the multi-partite state vector or density matrix *A* in the orthonormal basis or rank-1 projectors specified by the columns of the matrix *V*.

See also

```
qpp::measure_seq()
```

Note

The dimension of V must match the dimension of target. The measurement is destructive, i.e. the measured subsystems are traced away.

Α	Eigen expression
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part *target* of the multi-partite state vector or density matrix *A* in the orthonormal basis or rank-1 projectors specified by the columns of the matrix *V*.

See also

```
qpp::measure_seq()
```

Note

The dimension of *V* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression	
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors	
target	Subsystem indexes that are measured	
d	Subsystem dimensions	

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

See also

qpp::measure()

Parameters

Α	Eigen expression
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

See also

qpp::measure()

Parameters

Α	Eigen expression
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|\text{mask}\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

Parameters

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

Returns

Multi-partite qudit state vector, as a complex dynamic column vector

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Multi-partite qudit state vector, as a complex dynamic column vector

6.1.3.99 modinv()

Modular inverse of a mod p.

See also

```
qpp::egcd()
```

Note

a and p must be co-prime

Parameters

а	Non-negative integer
р	Non-negative integer

Returns

```
Modular inverse a^{-1} \mod p
```

6.1.3.100 modmul()

```
bigint qpp::modmul (
                bigint a,
                bigint b,
                bigint p ) [inline]
```

Modular multiplication without overflow.

Computes $ab \bmod p$ without overflow

Parameters

а	Integer
b	Integer
р	Positive integer

Returns

 $ab \bmod p$ avoiding overflow

6.1.3.101 modpow()

```
bigint qpp::modpow (
          bigint a,
```

```
bigint n,
bigint p ) [inline]
```

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

Note

Uses qpp::modmul() that avoids overflows

Computes $a^n \bmod p$

Parameters

а	Non-negative integer
n	Non-negative integer
р	Strictly positive integer

Returns

```
a^n \bmod p
```

const std::vector< idx > & dims) [inline]

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

Parameters

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

6.1.3.104 multiidx2n()

Multi-index to non-negative integer index.

See also

```
qpp::n2multiidx()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

Parameters

midx	Multi-index
dims	Dimensions of the multi-partite system

Returns

Non-negative integer index

6.1.3.105 n2multiidx()

```
\label{eq:std::vector} $$ std::vector < idx > qpp::n2multiidx ($$ idx n,$$ const std::vector < idx > & dims ) [inline]
```

Non-negative integer index to multi-index.

See also

```
qpp::multiidx2n()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

Parameters

n	Non-negative integer index
dims	Dimensions of the multi-partite system

Returns

Multi-index of the same size as dims

6.1.3.106 negativity() [1/2]

Negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Negativity

6.1.3.107 negativity() [2/2]

```
template<typename Derived >
double qpp::negativity (
```

```
const Eigen::MatrixBase< Derived > & A, idx d = 2)
```

Negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Negativity

6.1.3.108 norm()

Frobenius norm.

Parameters

```
A Eigen expression
```

Returns

Frobenius norm of A

6.1.3.109 normalize()

Normalizes state vector (column or row vector) or density matrix.

Parameters

A Eigen expression

Normalized state vector or density matrix

```
6.1.3.110 omega()

cplx qpp::omega (
          idx D ) [inline]
```

D-th root of unity.

Parameters

D Non-negative integer

6.1.3.111 operator""" _i()

Returns

D-th root of unity $\exp(2\pi i/D)$

User-defined literal for complex $i = \sqrt{-1}$ (real overload)

Example:

```
cplx z = 4.5_i; // type of z is std::complex<double>
```

6.1.3.112 powm()

Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

See also

```
qpp::spectralpowm()
```

Explicitly multiplies the matrix A with itself n times. By convention $A^0 = I$.

Α	Eigen expression
n	Non-negative integer

Returns

Matrix power A^n , as a dynamic matrix over the same scalar field as A

6.1.3.113 prj()

Projector.

Normalized projector onto state vector

Parameters

```
A Eigen expression
```

Returns

Projector onto the state vector A, or the matrix Zero if A has norm zero (i.e. smaller than qpp::eps), as a dynamic matrix over the same scalar field as A

6.1.3.114 prod() [1/3]

Element-wise product of A.

Parameters

```
A Eigen expression
```

Returns

Element-wise product of A, as a scalar over the same scalar field as A

Element-wise product of an STL-like range.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

InputIterator last)

Returns

Element-wise product of the range, as a scalar over the same scalar field as the range

Element-wise product of the elements of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Element-wise product of the elements of the container, as a scalar over the same scalar field as the container

See also

Partial trace.

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Returns

Partial trace $Tr_{subsys}(\cdot)$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

Partial trace.

See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial trace $Tr_{subsys}(\cdot)$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

```
6.1.3.119 ptrace1() [1/2]
```

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_A(\cdot)$ over the first subsytem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.120 ptrace1() [2/2]

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_A(\cdot)$ over the first subsystem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.121 ptrace2() [1/2]

Partial trace.

See also

```
qpp::ptrace1()
```

Partial trace over the second subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_B(\cdot)$ over the second subsytem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.122 ptrace2() [2/2]

Partial trace.

See also

qpp::ptrace1()

Partial trace over the second subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_B(\cdot)$ over the second subsytem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.123 ptranspose() [1/2]

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::ptranspose (
```

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & target,
const std::vector< idx > & dims )
```

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.3.124 ptranspose() [2/2]

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.3.125 QFT()

```
template<typename Derived >
dyn_col_vect<typename Derived::Scalar> qpp::QFT (
```

```
const Eigen::MatrixBase< Derived > & A, idx d = 2, bool swap = true)
```

Qudit quantum Fourier transform.

Parameters

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Qudit quantum Fourier transform applied on A

6.1.3.126 qmutualinfo() [1/2]

Quantum mutual information between 2 subsystems of a composite system.

Parameters

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
dims	Dimensions of the multi-partite system

Returns

Mutual information between the 2 subsystems

6.1.3.127 qmutualinfo() [2/2]

Quantum mutual information between 2 subsystems of a composite system.

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
d	Subsystem dimensions

Returns

Mutual information between the 2 subsystems

Generates a random real number uniformly distributed in the interval [a, b)

Parameters

a	ì	Beginning of the interval, belongs to it
b)	End of the interval, does not belong to it

Returns

Random real number (double) uniformly distributed in the interval [a, b)

Generates a random big integer uniformly distributed in the interval [a, b].

Note

To avoid ambiguity with double qpp::rand(double, double) cast at least one of the arguments to qpp::bigint

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

Random big integer uniformly distributed in the interval [a, b]

Generates a random matrix with entries uniformly distributed in the interval [a, b)

If complex, then both real and imaginary parts are uniformly distributed in [a, b)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries uniformly distributed in [-1,1)
dmat mat = rand<dmat>(3, 3, -1, 1);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd,
// with entries (both real and imaginary) uniformly distributed in [-1,1)
cmat mat = rand<cmat>(3, 3, -1, 1);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Returns

Random complex matrix

6.1.3.133 randH()

```
cmat qpp::randH (
    idx D = 2) [inline]
```

Generates a random Hermitian matrix.

Parameters

D Dimension of the Hilbert space

Random Hermitian matrix

6.1.3.134 randidx()

```
idx qpp::randidx (
        idx a = std::numeric_limits<idx>::min(),
        idx b = std::numeric_limits<idx>::max() ) [inline]
```

Generates a random index (idx) uniformly distributed in the interval [a, b].

Parameters

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

Returns

Random index (idx) uniformly distributed in the interval [a, b]

6.1.3.135 randket()

```
ket qpp::randket (
idx D = 2) [inline]
```

Generates a random normalized ket (pure state vector)

Parameters

D Dimension of the Hilbert space

Returns

Random normalized ket

6.1.3.136 randkraus()

```
std::vector<cmat> qpp::randkraus (
    idx N,
    idx D = 2 ) [inline]
```

Generates a set of random Kraus operators.

Note

The set of Kraus operators satisfy the closure condition $\sum_i K_i^\dagger K_i = I$

Parameters

N	Number of Kraus operators
D	Dimension of the Hilbert space

Returns

Set of N Kraus operators satisfying the closure condition

Generates a random matrix with entries normally distributed in N(mean, sigma)

If complex, then both real and imaginary parts are normally distributed in N(mean, sigma)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries normally distributed in N(0,2)
dmat mat = randn<dmat>(3, 3, 0, 2);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Returns

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd, 
// with entries (both real and imaginary) normally distributed in N(0,2) cmat mat = randn<cmat>(3, 3, 0, 2);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Returns

Random complex matrix

Generates a random real number (double) normally distributed in N(mean, sigma)

Parameters

mean	Mean
sigma	Standard deviation

Returns

Random real number normally distributed in N(mean, sigma)

6.1.3.141 randperm()

```
std::vector<idx> qpp::randperm (
    idx N ) [inline]
```

Generates a random uniformly distributed permutation.

Uses Knuth shuffle method (as implemented by std::shuffle), so that all permutations are equally probable

Parameters

```
N Size of the permutation
```

Returns

Random permutation of size N

6.1.3.142 randprime()

```
bigint qpp::randprime (
          bigint a,
          bigint b,
          idx N = 1000 ) [inline]
```

Generates a random big prime uniformly distributed in the interval [a, b].

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it
N	Maximum number of candidates

Random big integer uniformly distributed in the interval [a, b]

6.1.3.143 randprob()

```
\label{eq:std::vector} $$ \std::vector<double> qpp::randprob ( idx N) [inline]
```

Generates a random probability vector uniformly distributed over the probability simplex.

Parameters

N Size of the probability vector

Returns

Random probability vector

6.1.3.144 randrho()

```
cmat qpp::randrho (
    idx D = 2 ) [inline]
```

Generates a random density matrix.

Parameters

D Dimension of the Hilbert space

Returns

Random density matrix

6.1.3.145 randU()

```
cmat qpp::randU (
    idx D = 2) [inline]
```

Generates a random unitary matrix.

D Dimension of the Hilbert space

Returns

Random unitary

6.1.3.146 randV()

Generates a random isometry matrix.

Parameters

Din	Size of the input Hilbert space
Dout	Size of the output Hilbert space

Returns

Random isometry matrix

```
6.1.3.147 renyi() [1/2]
```

Renyi- α entropy of the density matrix ${\it A}$, for $\alpha \geq 0$.

Note

When $\alpha \to 1$ the Renyi entropy converges to the von-Neumann entropy, with the logarithm in base 2

Α	Eigen expression
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

Renyi- α entropy, with the logarithm in base 2

Renyi- α entropy of the probability distribution *prob*, for $\alpha \geq 0$.

Note

When $\alpha \to 1$ the Renyi entropy converges to the Shannon entropy, with the logarithm in base 2

Parameters

prob	Real probability vector
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

Returns

Renyi- α entropy, with the logarithm in base 2

6.1.3.149 reshape()

Reshape.

Uses column-major order when reshaping (same as MATLAB)

Α	Eigen expression
rows	Number of rows of the reshaped matrix
cols	Number of columns of the reshaped matrix

Reshaped matrix with rows rows and cols columns, as a dynamic matrix over the same scalar field as A

6.1.3.150 rho2bloch()

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

See also

qpp::bloch2rho()

Note

It is implicitly assumed that the density matrix is Hermitian

Parameters

A Eigen expression

Returns

3-dimensional Bloch vector

6.1.3.151 rho2pure()

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

Note

No purity check is done, the input state A must have rank one, otherwise the function returns the first non-zero eigenvector of A

Parameters

A Eigen expression, assumed to be proportional to a projector onto a pure state, i.e. A is assumed to have rank one

The unique non-zero eigenvector of A (up to a phase), as a dynamic column vector over the same scalar field as A

6.1.3.152 save()

Saves Eigen expression to a binary file (internal format) in double precision.

See also

qpp::load()

Parameters

Α	Eigen expression
fname	Output file name

6.1.3.153 saveMATLAB() [1/2]

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

qpp::loadMATLAB()

Template Parameters

Complex Eigen type

Α	Eigen expression over the complex field
---	---

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be saved
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details

6.1.3.154 saveMATLAB() [2/2]

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

qpp::loadMATLAB()

Template Parameters

Npn-complex	Eigen type
-------------	------------

Parameters

Α	Non-complex Eigen expression	
mat_file	MATALB .mat file	
var_name	Variable name in the .mat file representing the matrix to be saved	
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details	

6.1.3.155 schatten()

Schatten matrix norm.

Α	Eigen expression
p	Real number, greater or equal to 1, use qpp::infty for $p=\infty$

Schatten-p matrix norm of A

Schmidt basis on Alice side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix \boldsymbol{U} whose columns represent the Schmidt basis vectors on Alice side.

Schmidt basis on Alice side.

idx d = 2)

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix U whose columns represent the Schmidt basis vectors on Alice side.

6.1.3.158 schmidtB() [1/2] template<typename Derived > cmat qpp::schmidtB (

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & dims )
```

Schmidt basis on Bob side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

Schmidt basis on Bob side.

idx d = 2)

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.161 schmidtcoeffs() [2/2]

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.162 schmidtprobs() [1/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.3.163 schmidtprobs() [2/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.3.164 sigma()

Standard deviation.

prob	Real probability vector representing the probability distribution of X
X	Real random variable values represented by an STL-like container

Returns

Standard deviation of X

6.1.3.165 sinm()

Matrix sin.

Parameters

A Eigen expression

Returns

Matrix sine of A

6.1.3.166 spectralpowm()

Matrix power.

See also

qpp::powm()

Uses the spectral decomposition of \emph{A} to compute the matrix power. By convention $\emph{A}^0 = \emph{I}$.

Α	Eigen expression
Z	Complex number

Matrix power A^z

6.1.3.167 sqrtm()

Matrix square root.

Parameters

```
A Eigen expression
```

Returns

Matrix square root of A

6.1.3.168 sum() [1/3]

Element-wise sum of A.

Parameters

```
A Eigen expression
```

Returns

Element-wise sum of A, as a scalar over the same scalar field as A

6.1.3.169 sum() [2/3]

Element-wise sum of an STL-like range.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Element-wise sum of the range, as a scalar over the same scalar field as the range

Element-wise sum of the elements of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Element-wise sum of the elements of the container, as a scalar over the same scalar field as the container

6.1.3.171 super2choi()

Converts superoperator matrix to Choi matrix.

See also

qpp::choi2super()

Parameters

A Superoperator matrix

Returns

Choi matrix

6.1.3.172 svals()

Singular values.

Parameters

A Eigen expression

Returns

Singular values of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.173 svd()

Full singular value decomposition.

Parameters

A Eigen expression

Returns

Tuple of: 1. Left sigular vectors of A, as columns of a complex dynamic matrix, 2. Singular values of A, ordered in decreasing order, as a real dynamic column vector, and 3. Right singular vectors of A, as columns of a complex dynamic matrix

6.1.3.174 svdU()

Left singular vectors.

Parameters

```
A Eigen expression
```

Returns

Complex dynamic matrix, whose columns are the left singular vectors of A

6.1.3.175 svdV()

Right singular vectors.

Parameters

```
A Eigen expression
```

Returns

Complex dynamic matrix, whose columns are the right singular vectors of A

6.1.3.176 syspermute() [1/2]

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Parameters

Α	Eigen expression
perm	Permutation
dims	Dimensions of the multi-partite system

Returns

Permuted system, as a dynamic matrix over the same scalar field as A

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Parameters

Α	Eigen expression	
perm	Permutation	
d	Subsystem dimensions	

Returns

Permuted system, as a dynamic matrix over the same scalar field as A

6.1.3.178 TFQ()

Inverse (adjoint) qudit quantum Fourier transform.

Parameters

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Inverse (adjoint) qudit quantum Fourier transform applied on A

6.1.3.179 trace()

Trace.

Parameters

```
A Eigen expression
```

Returns

Trace of A, as a scalar over the same scalar field as A

6.1.3.180 transpose()

Transpose.

Parameters

```
A Eigen expression
```

Returns

Transpose of A, as a dynamic matrix over the same scalar field as A

```
6.1.3.181 tsallis() [1/2] template<typename Derived > double qpp::tsallis ( const Eigen::MatrixBase< Derived > & A, double q)
```

Tsallis- q entropy of the density matrix A, for $q \ge 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the von-Neumann entropy, with the logarithm in base e

Parameters

Α	Eigen expression
q	Non-negative real number

Returns

Tsallis- q entropy

Tsallis- q entropy of the probability distribution *prob*, for $q \ge 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the Shannon entropy, with the logarithm in base e

Parameters

prob	Real probability vector
q	Non-negative real number

Returns

Tsallis- q entropy

6.1.3.183 uniform()

```
std::vector<double> qpp::uniform (
    idx N ) [inline]
```

Uniform probability distribution vector.

Parameters

N Size of the alphabet

Returns

Real vector consisting of a uniform distribution of size N

6.1.3.184 var()

Variance.

Parameters

prob	Real probability vector representing the probability distribution of X
Χ	Real random variable values represented by an STL-like container

Returns

Variance of X

6.1.3.185 x2contfrac()

Simple continued fraction expansion.

See also

```
qpp::contfrac2x()
```

Parameters

Χ	Real number
Ν	Maximum number of terms in the expansion
cut	Stop the expansion when the next term is greater than cut

Returns

Integer vector containing the simple continued fraction expansion of x. If there are M less than N terms in the expansion, a shorter vector with M components is returned.

6.1.4 Variable Documentation

6.1.4.1 chop

```
constexpr double qpp::chop = 1e-10
```

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

6.1.4.2 ee

```
constexpr double qpp::ee = 2.718281828459045235360287471352662497
```

Base of natural logarithm, e.

6.1.4.3 eps

```
constexpr double qpp::eps = std::numeric_limits<double>::epsilon()
```

Used to decide whether a number or expression in double precision is zero or not for the purpose of a specific computation.

Example:

```
if(std::abs(x) < qpp::eps) // x is zero</pre>
```

6.1.4.4 idx_infty

```
const idx qpp::idx_infty = static_cast<idx>(-1)
```

Used to denote the largest unsigned index.

6.1.4.5 infty

```
constexpr double qpp::infty = std::numeric_limits<double>::max()
```

Used to denote infinity in double precision.

6.1.4.6 maxn

```
constexpr idx qpp::maxn = 64
```

Maximum number of allowed qubits/qudits (subsystems)

Used internally to allocate arrays on the stack (for performance reasons):

6.1.4.7 pi

```
constexpr double qpp::pi = 3.141592653589793238462643383279502884
```

 π

6.2 qpp::exception Namespace Reference

Quantum++ exception hierarchy namespace.

Classes

• class CustomException

Custom exception.

· class DimsInvalid

Invalid dimension(s) exception.

· class DimsMismatchCvector

Dimension(s) mismatch column vector size exception.

• class DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

· class DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

· class DimsMismatchVector

Dimension(s) mismatch vector size exception.

class DimsNotEqual

Dimensions not equal exception.

· class Duplicates

System (e.g. std::vector) has duplicates exception.

class Exception

Base class for generating Quantum++ custom exceptions.

class InvalidIterator

Invalid iterator.

• class MatrixMismatchSubsys

Matrix mismatch subsystems exception.

• class MatrixNotCvector

Matrix is not a column vector exception.

class MatrixNotRvector

Matrix is not a row vector exception.

class MatrixNotSquare

Matrix is not square exception.

· class MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

class MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

· class MatrixNotSquareNorVector

Matrix is not square nor vector exception.

· class MatrixNotVector

Matrix is not a vector exception.

class NoCodeword

Codeword does not exist exception.

· class NotBipartite

Not bi-partite exception.

· class NotImplemented

Code not yet implemented.

class NotQubitCvector

Column vector is not 2 x 1 exception.

class NotQubitMatrix

Matrix is not 2 x 2 exception.

· class NotQubitRvector

Row vector is not 1 x 2 exception.

class NotQubitSubsys

Subsystems are not qubits exception.

class NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

class OutOfRange

Argument out of range exception.

class PermInvalid

Invalid permutation exception.

· class PermMismatchDims

Permutation mismatch dimensions exception.

class QuditAlreadyMeasured

Qudit was already measured exception.

· class SizeMismatch

Size mismatch exception.

• class SubsysMismatchDims

Subsystems mismatch dimensions exception.

class TypeMismatch

Type mismatch exception.

class UndefinedType

Not defined for this type exception.

• class Unknown

Unknown exception.

class ZeroSize

Object has zero size exception.

6.2.1 Detailed Description

Quantum++ exception hierarchy namespace.

6.3 qpp::experimental Namespace Reference

Experimental/test functions/classes, do not use or modify.

6.3.1 Detailed Description

Experimental/test functions/classes, do not use or modify.

6.4 qpp::internal Namespace Reference

Internal utility functions, do not use them directly or modify them.

Classes

- struct Display Impl
- · class IOManipEigen
- · class IOManipPointer
- · class IOManipRange
- · class Singleton

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Functions

- void n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- $\bullet \ \ \text{template}{<} \text{typename Derived} >$

bool check_square_mat (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ \mathsf{template} \mathord{<} \mathsf{typename} \ \mathsf{Derived} >$

bool bool check_vector (const Eigen::MatrixBase Derived > &A)

• template<typename Derived >

bool check_rvector (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

bool check_cvector (const Eigen::MatrixBase< Derived > &A)

• template<typename T >

bool check_nonzero_size (const T &x) noexcept

- template<typename T1 , typename T2 >

bool check_matching_sizes (const T1 &lhs, const T2 &rhs) noexcept

- bool check_dims (const std::vector< idx > &dims)
- template<typename Derived >

 $bool\ check_dims_match_mat\ (const\ std::vector < idx > \&dims,\ const\ Eigen::MatrixBase < Derived > \&A)$

• template<typename Derived >

bool check_dims_match_cvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool check dims match rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- bool check_eq_dims (const std::vector< idx > &dims, idx dim) noexcept
- bool check_no_duplicates (std::vector< idx > v)
- bool check_subsys_match_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)

```
    template < typename Derived >
        bool check_qubit_matrix (const Eigen::MatrixBase < Derived > &A) noexcept
```

• template<typename Derived >

bool check_qubit_cvector (const Eigen::MatrixBase< Derived > &A) noexcept

template<typename Derived >
 bool check_qubit_rvector (const Eigen::MatrixBase< Derived > &A) noexcept

template<typename Derived >
 bool check_qubit_vector (const Eigen::MatrixBase< Derived > &A) noexcept

bool check_perm (const std::vector< idx > &perm)

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > kron2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::
 MatrixBase< Derived2 > &B)

template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > dirsum2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen
 ::MatrixBase< Derived2 > &B)

template<typename T > void variadic_vector_emplace (std::vector< T > &)

- $\begin{tabular}{ll} & \textbf{template}$<&typename T$, typename First , typename... Args>&void variadic_vector_emplace (std::vector< T>&v, First &&first, Args &&... args) \\ \end{tabular}$
- idx get num subsys (idx D, idx d)
- idx get_dim_subsys (idx sz, idx N)

6.4.1 Detailed Description

Internal utility functions, do not use them directly or modify them.

6.4.2 Function Documentation

6.4.2.1 check_cvector()

6.4.2.2 check_dims()

```
bool qpp::internal::check_dims (  const \ std::vector < \ idx \ > \ \& \ dims \ ) \quad [inline]
```

6.4.2.3 check_dims_match_cvect()

6.4.2.4 check_dims_match_mat()

6.4.2.5 check_dims_match_rvect()

6.4.2.6 check_eq_dims()

6.4.2.7 check_matching_sizes()

6.4.2.8 check_no_duplicates()

```
bool qpp::internal::check_no_duplicates ( {\tt std::vector} < {\tt idx} \, > \, v \; ) \quad [{\tt inline}]
```

```
6.4.2.9 check_nonzero_size()
template<typename T >
bool qpp::internal::check_nonzero_size (
            const T & x ) [noexcept]
6.4.2.10 check_perm()
bool qpp::internal::check_perm (
            const std::vector< idx > & perm ) [inline]
6.4.2.11 check_qubit_cvector()
template<typename Derived >
bool qpp::internal::check_qubit_cvector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.12 check_qubit_matrix()
template<typename Derived >
bool qpp::internal::check_qubit_matrix (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.13 check_qubit_rvector()
template<typename Derived >
bool qpp::internal::check_qubit_rvector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.14 check_qubit_vector()
template<typename Derived >
bool qpp::internal::check_qubit_vector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
```

```
6.4.2.15 check_rvector()
```

```
template<typename Derived >
bool qpp::internal::check_rvector (
            const Eigen::MatrixBase< Derived > & A )
6.4.2.16 check_square_mat()
template<typename Derived >
bool qpp::internal::check_square_mat (
            const Eigen::MatrixBase< Derived > & A )
6.4.2.17 check_subsys_match_dims()
bool qpp::internal::check_subsys_match_dims (
            const std::vector< idx > & subsys,
            const std::vector< idx > & dims ) [inline]
6.4.2.18 check_vector()
template<typename Derived >
bool qpp::internal::check_vector (
            const Eigen::MatrixBase< Derived > & A )
6.4.2.19 dirsum2()
template<typename Derived1 , typename Derived2 >
dyn_mat<typename Derived1::Scalar> qpp::internal::dirsum2 (
            const Eigen::MatrixBase< Derived1 > & A,
            const Eigen::MatrixBase< Derived2 > & B )
6.4.2.20 get_dim_subsys()
idx qpp::internal::get_dim_subsys (
            idx sz,
             idx N ) [inline]
```

6.4.2.21 get_num_subsys()

```
idx qpp::internal::get_num_subsys (
            idx D,
             idx d ) [inline]
6.4.2.22 kron2()
template<typename Derived1 , typename Derived2 >
dyn_mat<typename Derived1::Scalar> qpp::internal::kron2 (
            const Eigen::MatrixBase< Derived1 > & A,
             const Eigen::MatrixBase< Derived2 > & B )
6.4.2.23 multiidx2n()
idx qpp::internal::multiidx2n (
             const idx *const midx,
             idx numdims,
             const idx *const dims ) [inline], [noexcept]
6.4.2.24 n2multiidx()
void qpp::internal::n2multiidx (
             idx n,
             idx numdims,
             const idx *const dims,
             idx * result ) [inline], [noexcept]
6.4.2.25 variadic_vector_emplace() [1/2]
template<typename T >
void qpp::internal::variadic_vector_emplace (
            std::vector< T > & )
6.4.2.26 variadic_vector_emplace() [2/2]
template<typename T , typename First , typename... Args>
void qpp::internal::variadic_vector_emplace (
             std::vector< T > & v,
             First && first,
             Args &&... args )
```

6.5 qpp::literals Namespace Reference

Functions

```
• constexpr cplx operator"" _i (unsigned long long int x) noexcept \textit{User-defined literal for complex } i = \sqrt{-1} \textit{ (integer overload)}
```

```
template<char... Bits>
ket operator"" _ket ()
```

Multi-partite qubit ket user-defined literal.

template<char... Bits> bra operator"" _bra ()

Multi-partite qubit bra user-defined literal.

template<char... Bits> cmat operator"" _prj ()

Multi-partite qubit projector user-defined literal.

6.5.1 Function Documentation

```
6.5.1.1 operator"""_bra()

template<char... Bits>
bra qpp::literals::operator"" _bra ( )
```

Multi-partite qubit bra user-defined literal.

See also

```
qpp::mket() and qpp::adjoint()
```

Constructs the multi-partite qubit bra $\langle \mathrm{Bits}|$

Template Parameters

```
Bits String of binary numbers representing the qubit bra
```

Returns

Multi-partite qubit bra, as a complex dynamic row vector

User-defined literal for complex $i = \sqrt{-1}$ (integer overload)

Example:

```
cplx z = 4_i; // type of z is std::complex<double>
```

6.5.1.3 operator""" _ket()

```
template<char... Bits>
ket qpp::literals::operator"" _ket ( )
```

Multi-partite qubit ket user-defined literal.

See also

qpp::mket()

Constructs the multi-partite qubit ket $|Bits\rangle$

Template Parameters

Bits	String of binary numbers representing the qubit ket
------	---

Returns

Multi-partite qubit ket, as a complex dynamic column vector

6.5.1.4 operator""" _prj()

```
template<char... Bits>
cmat qpp::literals::operator"" _prj ( )
```

Multi-partite qubit projector user-defined literal.

See also

qpp::mprj()

Constructs the multi-partite qubit projector $|\mathrm{Bits}\rangle\langle\mathrm{Bits}|$ (in the computational basis)

Template Parameters

Bits String of binary numbers representing the qubit state to project on

\mathbf{L}	ΔT	 rn	c

Multi-partite qubit projector, as a complex dynamic matrix

Chapter 7

Class Documentation

7.1 qpp::Bit_circuit Class Reference


Classical reversible circuit simulator.

#include <classes/reversible.h>

Inheritance diagram for qpp::Bit_circuit:



Collaboration diagram for qpp::Bit_circuit:



Classes

struct Gate_count

Public Member Functions

- Bit_circuit (const Dynamic_bitset &dynamic_bitset)
 - Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.
- Bit_circuit & X (idx pos)

Bit flip.

Bit_circuit & NOT (idx pos)

Bit flip

• Bit_circuit & CNOT (const std::vector< idx > &pos)

Controlled-NOT.

• Bit_circuit & TOF (const std::vector< idx > &pos)

Toffoli gate.

Bit_circuit & SWAP (const std::vector < idx > &pos)

Swap bits.

• Bit_circuit & FRED (const std::vector< idx > &pos)

Fredkin gate (Controlled-SWAP)

• Bit_circuit & reset () noexcept

Reset the circuit all zero, clear all gates.

Dynamic_bitset (idx N)

Inherited constructor.

Public Attributes

struct qpp::Bit_circuit::Gate_count gate_count
 Gate counters.

Additional Inherited Members

7.1.1 Detailed Description

Classical reversible circuit simulator.

7.1.2 Constructor & Destructor Documentation

7.1.2.1 Bit_circuit()

Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.

Parameters

7.1.3 Member Function Documentation

7.1.3.1 CNOT()

Controlled-NOT.

Parameters

```
pos Bit position in the circuit
```

Returns

Reference to the current instance

7.1.3.2 Dynamic_bitset()

```
qpp::Dynamic_bitset::Dynamic_bitset [inline], [explicit]
```

Inherited constructor.

7.1.3.3 FRED()

Fredkin gate (Controlled-SWAP)

Parameters

pos Bit positions in the circuit, in the order control-target-target

Returns

Reference to the current instance

7.1.3.4 NOT()

```
Bit_circuit& qpp::Bit_circuit::NOT (
        idx pos ) [inline]
```

Bit flip.

See also

qpp::Bit_circuit::X()

Parameters

pos Bit position in the circuit

Returns

Reference to the current instance

7.1.3.5 reset()

```
Bit_circuit& qpp::Bit_circuit::reset ( ) [inline], [noexcept]
```

Reset the circuit all zero, clear all gates.

Returns

Reference to the current instance

7.1.3.6 SWAP()

Swap bits.

Parameters

pos Bit positions in the circuit

Returns

Reference to the current instance

7.1.3.7 TOF()

Toffoli gate.

Parameters

pos | Bit positions in the circuit, in the order control-control-target

Returns

Reference to the current instance

7.1.3.8 X()

```
Bit_circuit& qpp::Bit_circuit::X (
        idx pos ) [inline]
```

Bit flip.

See also

qpp::Bit_circuit::NOT()

Parameters

pos Bit position in the circuit

Returns

Reference to the current instance

7.1.4 Member Data Documentation

7.1.4.1 gate_count

```
struct qpp::Bit_circuit::Gate_count qpp::Bit_circuit::gate_count
```

Gate counters.

The documentation for this class was generated from the following file:


• classes/reversible.h

7.2 qpp::Codes Class Reference


const Singleton class that defines quantum error correcting codes

```
#include <classes/codes.h>
```

Inheritance diagram for qpp::Codes:



Collaboration diagram for qpp::Codes:



Public Types

• enum Type { Type::FIVE_QUBIT = 1, Type::SEVEN_QUBIT_STEANE, Type::NINE_QUBIT_SHOR }

Code types, add more codes here if needed.

Public Member Functions

ket codeword (Type type, idx i) const
 Returns the codeword of the specified code type.

Private Member Functions

• Codes ()

Default constructor.

∼Codes ()=default

Default destructor.

Friends

class internal::Singleton < const Codes >

Additional Inherited Members

7.2.1 Detailed Description

const Singleton class that defines quantum error correcting codes

7.2.2 Member Enumeration Documentation

7.2.2.1 Type

```
enum qpp::Codes::Type [strong]
```

Code types, add more codes here if needed.

See also

```
qpp::Codes::codeword()
```

Enumerator

FIVE_QUBIT	[[5,1,3]] qubit code
SEVEN_QUBIT_STEANE	[[7,1,3]] Steane qubit code
NINE_QUBIT_SHOR	[[9,1,3]] Shor qubit code

7.2.3 Constructor & Destructor Documentation

7.2.3.1 Codes()

```
qpp::Codes::Codes ( ) [inline], [private]
```

Default constructor.

7.2.3.2 ∼Codes()

```
qpp::Codes::~Codes ( ) [private], [default]
```

Default destructor.

7.2.4 Member Function Documentation

7.2.4.1 codeword()

Returns the codeword of the specified code type.

See also

qpp::Codes::Type

Parameters

type	Code type
i	Codeword index

Returns

i-th codeword of the code type

7.2.5 Friends And Related Function Documentation

7.2.5.1 internal::Singleton < const Codes >

```
friend class internal::Singleton< const Codes > [friend]
```

The documentation for this class was generated from the following file:

classes/codes.h

7.3 qpp::exception::CustomException Class Reference


Custom exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::CustomException:



Collaboration diagram for qpp::exception::CustomException:



Public Member Functions

· CustomException (const std::string &where, const std::string &what)

Private Member Functions

std::string type_description () const override
 Exception type description.

Private Attributes

std::string what_{{}}

7.3.1 Detailed Description

Custom exception.

Custom exception, the user must provide a custom message

7.3.2 Constructor & Destructor Documentation

7.3.2.1 CustomException()

7.3.3 Member Function Documentation

7.3.3.1 type_description()

```
std::string qpp::exception::CustomException::type_description ( ) const [inline], [override],
[private], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

7.3.4 Member Data Documentation

7.3.4.1 what_

```
std::string qpp::exception::CustomException::what_ {} [private]
```

The documentation for this class was generated from the following file:


· classes/exception.h

7.4 qpp::exception::DimsInvalid Class Reference

Invalid dimension(s) exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsInvalid:



Collaboration diagram for qpp::exception::DimsInvalid:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.4.1 Detailed Description

Invalid dimension(s) exception.

std::vector<idx> of dimensions has zero size or contains zeros

7.4.2 Member Function Documentation

7.4.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.4.2.2 type_description()

std::string qpp::exception::DimsInvalid::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.5 qpp::exception::DimsMismatchCvector Class Reference


Dimension(s) mismatch column vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchCvector:



Collaboration diagram for qpp::exception::DimsMismatchCvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.5.1 Detailed Description

Dimension(s) mismatch column vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a column vector)

7.5.2 Member Function Documentation

7.5.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred
--

7.5.2.2 type_description()

std::string qpp::exception::DimsMismatchCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.6 qpp::exception::DimsMismatchMatrix Class Reference


Dimension(s) mismatch matrix size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchMatrix:



Collaboration diagram for qpp::exception::DimsMismatchMatrix:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.6.1 Detailed Description

Dimension(s) mismatch matrix size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of rows of the Eigen::Matrix (assumed to be a square matrix)

7.6.2 Member Function Documentation

7.6.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred
--

7.6.2.2 type_description()

```
std::string qpp::exception::DimsMismatchMatrix::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

7.7 qpp::exception::DimsMismatchRvector Class Reference


Dimension(s) mismatch row vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchRvector:



Collaboration diagram for qpp::exception::DimsMismatchRvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.7.1 Detailed Description

Dimension(s) mismatch row vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row vector)

7.7.2 Member Function Documentation

7.7.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

Text representing where the exception of	d
--	---

7.7.2.2 type_description()

std::string qpp::exception::DimsMismatchRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

7.8 qpp::exception::DimsMismatchVector Class Reference

Dimension(s) mismatch vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchVector:



Collaboration diagram for qpp::exception::DimsMismatchVector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.8.1 Detailed Description

Dimension(s) mismatch vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row/column vector)

7.8.2 Member Function Documentation

7.8.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
******	Toxt representing where the exception eccurred

7.8.2.2 type_description()

```
std::string qpp::exception::DimsMismatchVector::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.9 qpp::exception::DimsNotEqual Class Reference


Dimensions not equal exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsNotEqual:



Collaboration diagram for qpp::exception::DimsNotEqual:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.9.1 Detailed Description

Dimensions not equal exception.

Local/global dimensions are not equal

7.9.2 Member Function Documentation

7.9.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.9.2.2 type_description()

std::string qpp::exception::DimsNotEqual::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

7.10 qpp::internal::Display_Impl_ Struct Reference

```
#include <internal/util.h>
```

Inheritance diagram for qpp::internal::Display_Impl_:



Public Member Functions

template<typename T >
 std::ostream & display_impl_ (const T &A, std::ostream &os, double chop=qpp::chop) const

7.10.1 Member Function Documentation

7.10.1.1 display_impl_()

The documentation for this struct was generated from the following file:


• internal/util.h

7.11 qpp::exception::Duplicates Class Reference


System (e.g. std::vector) has duplicates exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Duplicates:



Collaboration diagram for qpp::exception::Duplicates:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.11.1 Detailed Description

System (e.g. std::vector) has duplicates exception.

7.11.2 Member Function Documentation

7.11.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.11.2.2 type_description()

```
std::string qpp::exception::Duplicates::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.12 qpp::Dynamic_bitset Class Reference

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std:bitset < N >)

#include <classes/reversible.h>

Inheritance diagram for qpp::Dynamic_bitset:



Collaboration diagram for qpp::Dynamic_bitset:



Public Types

- using value_type = unsigned int
 Type of the storage elements.
- using storage_type = std::vector< value_type >
 Type of the storage.

Public Member Functions

• Dynamic bitset (idx N)

Constructor, initializes all bits to false (zero)

virtual ~Dynamic bitset ()=default

Default virtual destructor.

const storage_type & data () const

Raw storage space of the bitset.

• idx size () const noexcept

Number of bits stored in the bitset.

• idx storage_size () const noexcept

Size of the underlying storage space (in units of value_type, unsigned int by default)

· idx count () const noexcept

Number of bits set to one in the bitset (Hamming weight)

bool get (idx pos) const noexcept

The value of the bit at position pos.

· bool none () const noexcept

Checks whether none of the bits are set.

• bool all () const noexcept

Checks whether all bits are set.

• bool any () const noexcept

Checks whether any bit is set.

Dynamic_bitset & set (idx pos, bool value=true)

Sets the bit at position pos.

Dynamic_bitset & set () noexcept

Set all bits to true.

• Dynamic bitset & rand (idx pos, double p=0.5)

Sets the bit at position pos according to a Bernoulli(p) distribution.

• Dynamic_bitset & rand (double p=0.5)

Sets all bits according to a Bernoulli(p) distribution.

Dynamic_bitset & reset (idx pos)

Sets the bit at position pos to false.

Dynamic_bitset & reset () noexcept

Sets all bits to false.

Dynamic_bitset & flip (idx pos)

Flips the bit at position pos.

· Dynamic bitset & flip () noexcept

Flips all bits.

• bool operator== (const Dynamic_bitset &rhs) const noexcept

Equality operator.

• bool operator!= (const Dynamic_bitset &rhs) const noexcept

Inequality operator.

• idx operator- (const Dynamic_bitset &rhs) const noexcept

Number of places the two bitsets differ (Hamming distance)

template < class CharT = char, class Traits = std::char_traits < CharT>, class Allocator = std::allocator < CharT>> std::basic_string < CharT, Traits, Allocator > to_string (CharT zero=CharT('0'), CharT one=CharT('1')) const String representation.

Protected Member Functions

- idx index_ (idx pos) const
 Index of the pos bit in the storage space.
- idx offset_ (idx pos) const

Offset of the pos bit in the storage space relative to its index.

Protected Attributes

```
• idx storage_size_
Storage size.
```

idx N

Number of bits.

std::vector< value_type > v_
 Storage space.

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display()* override, displays the bitset bit by bit

7.12.1 Detailed Description

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

7.12.2 Member Typedef Documentation

```
7.12.2.1 storage_type
```

```
using qpp::Dynamic_bitset::storage_type = std::vector<value_type>
```

Type of the storage.

7.12.2.2 value_type

```
using qpp::Dynamic_bitset::value_type = unsigned int
```

Type of the storage elements.

7.12.3 Constructor & Destructor Documentation

7.12.3.1 Dynamic_bitset()

Constructor, initializes all bits to false (zero)

Parameters

N Number of bits in the bitset

```
7.12.3.2 ~Dynamic_bitset()
```

```
virtual qpp::Dynamic_bitset::~Dynamic_bitset ( ) [virtual], [default]
```

Default virtual destructor.

7.12.4 Member Function Documentation

```
7.12.4.1 all()
```

```
bool qpp::Dynamic_bitset::all ( ) const [inline], [noexcept]
```

Checks whether all bits are set.

Returns

True if all of the bits are set

7.12.4.2 any()

```
bool qpp::Dynamic_bitset::any ( ) const [inline], [noexcept]
```

Checks whether any bit is set.

Returns

True if any of the bits is set

7.12.4.3 count()

```
idx qpp::Dynamic_bitset::count ( ) const [inline], [noexcept]
```

Number of bits set to one in the bitset (Hamming weight)

Returns

Hamming weight

7.12.4.4 data()

```
const storage_type& qpp::Dynamic_bitset::data ( ) const [inline]
```

Raw storage space of the bitset.

Returns

Const reference to the underlying storage space

7.12.4.5 display()

qpp::IDisplay::display() override, displays the bitset bit by bit

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.12.4.6 flip() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip (
        idx pos ) [inline]
```

Flips the bit at position pos.

Parameters

pos Position in the bitset

Returns

Reference to the current instance

```
7.12.4.7 flip() [2/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip ( ) [inline], [noexcept]
```

Flips all bits.

Returns

Reference to the current instance

7.12.4.8 get()

```
bool qpp::Dynamic_bitset::get (
          idx pos ) const [inline], [noexcept]
```

The value of the bit at position pos.

Parameters

pos	Position in the bitset
-----	------------------------

Returns

The value of the bit at position pos

7.12.4.9 index_()

Index of the pos bit in the storage space.

Parameters

```
pos Bit location
```

Returns

Index of the pos bit in the storage space

7.12.4.10 none()

```
bool qpp::Dynamic_bitset::none ( ) const [inline], [noexcept]
```

Checks whether none of the bits are set.

Returns

True if none of the bits are set

7.12.4.11 offset_()

Offset of the *pos* bit in the storage space relative to its index.

Parameters

```
pos Bit location
```

Returns

Offset of the pos bit in the storage space relative to its index

7.12.4.12 operator"!=()

Inequality operator.

Parameters

```
rhs Dynamic_bitset against which the inequality is being tested
```

Returns

True if the bitsets are not equal (bit by bit), false otherwise

7.12.4.13 operator-()

Number of places the two bitsets differ (Hamming distance)

Parameters

```
rhs Dynamic_bitset against which the Hamming distance is computed
```

Returns

Hamming distance

7.12.4.14 operator==()

Equality operator.

Parameters

```
rhs Dynamic_bitset against which the equality is being tested
```

Returns

True if the bitsets are equal (bit by bit), false otherwise

7.12.4.15 rand() [1/2]

```
Dynamic_bitset& qpp::Dynamic_bitset::rand (
    idx pos,
    double p = 0.5 ) [inline]
```

Sets the bit at position *pos* according to a Bernoulli(p) distribution.

Parameters

pos	Position in the bitset
р	Probability

Returns

Reference to the current instance

Sets all bits according to a Bernoulli(p) distribution.

Parameters

```
p Probability
```

Returns

Reference to the current instance

Sets the bit at position pos to false.

Parameters

```
pos Position in the bitset
```

Returns

Reference to the current instance

```
7.12.4.18 reset() [2/2]
Dynamic_bitset& qpp::Dynamic_bitset::reset ( ) [inline], [noexcept]
Sets all bits to false.
```

Returns

Reference to the current instance

```
7.12.4.19 set() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::set (
        idx pos,
        bool value = true ) [inline]
```

Sets the bit at position pos.

Parameters

pos	Position in the bitset
value	Bit value

Returns

Reference to the current instance

```
7.12.4.20 set() [2/2]
Dynamic_bitset& qpp::Dynamic_bitset::set ( ) [inline], [noexcept]
```

Set all bits to true.

Returns

Reference to the current instance

```
7.12.4.21 size()
```

```
idx qpp::Dynamic_bitset::size ( ) const [inline], [noexcept]
```

Number of bits stored in the bitset.

Returns

Number of bits stored in the bitset

```
7.12.4.22 storage_size()
```

```
idx qpp::Dynamic_bitset::storage_size ( ) const [inline], [noexcept]
```

Size of the underlying storage space (in units of value_type, unsigned int by default)

Returns

Size of the underlying storage space

7.12.4.23 to_string()

String representation.

Template Parameters

CharT	String character type
Traits	String traits
Allocator	String Allocator

Parameters

	Character representing the zero
one	Character representing the one

Returns

The bitset as a string

7.12.5 Member Data Documentation

```
7.12.5.1 N_
```

```
idx qpp::Dynamic_bitset::N_ [protected]
```

Number of bits.


7.12.5.2 storage_size_

```
idx qpp::Dynamic_bitset::storage_size_ [protected]
```

Storage size.

166	Class Documentation
7.12.5.3 v_	
<pre>std::vector<value_type> qpp::Dynamic_bitset::v_ [protected]</value_type></pre>	
Storage space.	
The documentation for this class was generated from the following file:	
• classes/reversible.h	
7.13 qpp::exception::Exception Class Reference	
Base class for generating Quantum++ custom exceptions.	
<pre>#include <classes exception.h=""></classes></pre>	

Inheritance diagram for qpp::exception::Exception:



Collaboration diagram for qpp::exception::Exception:



Public Member Functions

• Exception (const std::string &where)

Constructs an exception.

- virtual const char * what () const noexcept override

Overrides std::exception::what()

• virtual std::string type_description () const =0

Exception type description.

Private Attributes

- std::string where_
- std::string msg_

7.13.1 Detailed Description

Base class for generating Quantum++ custom exceptions.

Derive from this class if more exceptions are needed, making sure to override qpp::exception::Exception::type_description() in the derived class and to inherit the constructor qpp::exception::Exception::Exception(). Preferably keep your newly defined exception classes in the namespace qpp::exception.

Example:

7.13.2 Constructor & Destructor Documentation

7.13.2.1 Exception()

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.13.3 Member Function Documentation

7.13.3.1 type_description()

```
std::string qpp::exception::Exception::type_description ( ) const [inline], [pure virtual]
```

Exception type description.

Returns

Exception type description

Implemented in qpp::exception::InvalidIterator, qpp::exception::NotImplemented, qpp::exception::CustomException, qpp::exception::Duplicates, qpp::exception::QuditAlreadyMeasured, qpp::exception::UndefinedType, qpp::exception::SizeMismatch, qpp::exception::TypeMismatch, qpp::exception::OutOfRange, qpp::exception::NotOdeword, qpp::exception::NotBipartite, qpp::exception::NotQubitSubsys, qpp::exception::NotQubitVector, qpp::exception::NotQubitRvector, qpp::exception::NotQubitCvector qpp::exception::NotQubitMatrix, qpp::exception::PermMismatchDims, qpp::exception::PermInvalid, qpp::exception::SubsysMismatchEqpp::exception::DimsMismatchVector, qpp::exception::DimsMismatchCvector, qpp::exception::DimsMismatchMatrix, qpp::exception::DimsNotEqual, qpp::exception::DimsInvalid, qpp::exception::MatrixMismatchSu qpp::exception::MatrixNotSquareNorVector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::Unknown.

7.13.3.2 what()

virtual const char* qpp::exception::Exception::what () const [inline], [override], [virtual],
[noexcept]

Overrides std::exception::what()

Returns

Exception description

7.13.4 Member Data Documentation

```
7.13.4.1 msg_
```

std::string qpp::exception::Exception::msg_ [mutable], [private]

7.13.4.2 where_

std::string qpp::exception::Exception::where_ [private]

The documentation for this class was generated from the following file:

· classes/exception.h

7.14 qpp::Bit_circuit::Gate_count Struct Reference

```
#include <classes/reversible.h>
```

Public Attributes

- idx NOT = 0
- idx & X = NOT
- idx CNOT = 0
- idx SWAP = 0
- idx FRED = 0
- idx TOF = 0

7.14.1 Member Data Documentation

7.14.1.1 CNOT

```
idx qpp::Bit_circuit::Gate_count::CNOT = 0
```

7.14.1.2 FRED

```
idx qpp::Bit_circuit::Gate_count::FRED = 0
```

7.14.1.3 NOT

```
idx qpp::Bit_circuit::Gate_count::NOT = 0
```

7.14.1.4 SWAP

```
idx qpp::Bit_circuit::Gate_count::SWAP = 0
```

7.14.1.5 TOF

```
idx qpp::Bit_circuit::Gate_count::TOF = 0
```

7.14.1.6 X

```
idx& qpp::Bit_circuit::Gate_count::X = NOT
```

The documentation for this struct was generated from the following file:

• classes/reversible.h

7.15 qpp::Gates Class Reference


const Singleton class that implements most commonly used gates

#include <classes/gates.h>

Inheritance diagram for qpp::Gates:



Collaboration diagram for qpp::Gates:



Public Member Functions

- cmat Rn (double theta, const std::vector< double > &n) const
 Qubit rotation of theta about the 3-dimensional real (unit) vector n.
- cmat RX (double theta) const

Qubit rotation of theta about the X axis.

• cmat RY (double theta) const

Qubit rotation of theta about the Y axis.

cmat RZ (double theta) const

Qubit rotation of theta about the Z axis.

• cmat Zd (idx D=2) const

Generalized Z gate for qudits.

```
• cmat SWAPd (idx D=2) const
          SWAP gate for qudits.
    • cmat Fd (idx D=2) const
          Quantum Fourier transform gate for qudits.

    cmat MODMUL (idx a, idx N, idx n) const

          Modular multiplication gate for qubits Implements |x\rangle \longrightarrow |ax \bmod N\rangle.

    cmat Xd (idx D=2) const

          Generalized X gate for qudits.
    • template<typename Derived = Eigen::MatrixXcd>
      Derived Id (idx D=2) const
          Identity gate.

    template<typename Derived >

      dyn mat< typename Derived::Scalar > CTRL (const Eigen::MatrixBase< Derived > &A, const std::vector<
      idx > &ctrl, const std::vector < idx > &target, idx n, idx d=2) const
          Generates the multi-partite multiple-controlled-A gate in matrix form.

    template<typename Derived >

      dyn mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
      std::vector < idx > &dims) const
          Expands out.

    template<typename Derived >

      dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
      std::initializer list< idx > &dims) const
          Expands out.

    template<typename Derived >

      dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, idx n,
      idx d=2) const
          Expands out.
    • std::string get_name (const cmat &U) const
          Get the name of the most common qubit gates.
Public Attributes
    cmat Id2 {cmat::Identity(2, 2)}
          Identity gate.

    cmat H {cmat::Zero(2, 2)}

          Hadamard gate.
    cmat X {cmat::Zero(2, 2)}
          Pauli Sigma-X gate.

    cmat Y {cmat::Zero(2, 2)}

          Pauli Sigma-Y gate.

    cmat Z {cmat::Zero(2, 2)}

          Pauli Sigma-Z gate.

    cmat S {cmat::Zero(2, 2)}

          S gate.

    cmat T {cmat::Zero(2, 2)}

          T gate.

    cmat CNOT {cmat::Identity(4, 4)}

          Controlled-NOT control target gate.

    cmat CZ {cmat::Identity(4, 4)}

          Controlled-Phase gate.

    cmat CNOTba {cmat::Zero(4, 4)}
```

```
Controlled-NOT target->control gate.
```

• cmat SWAP {cmat::Identity(4, 4)}

SWAP gate.

• cmat TOF {cmat::ldentity(8, 8)}

Toffoli gate.

• cmat FRED {cmat::ldentity(8, 8)}

Fredkin gate.

Private Member Functions

• Gates ()

Initializes the gates.

∼Gates ()=default

Default destructor.

Friends

class internal::Singleton < const Gates >

Additional Inherited Members

7.15.1 Detailed Description

const Singleton class that implements most commonly used gates

7.15.2 Constructor & Destructor Documentation

```
7.15.2.1 Gates()
```

```
qpp::Gates::Gates ( ) [inline], [private]
```

Initializes the gates.

7.15.2.2 \sim Gates()

```
qpp::Gates::\sim Gates ( ) [private], [default]
```

Default destructor.

7.15.3 Member Function Documentation

7.15.3.1 CTRL()

Generates the multi-partite multiple-controlled-A gate in matrix form.

See also

```
qpp::applyCTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
n	Total number of subsystems
d	Subsystem dimensions

Returns

CTRL-A gate, as a matrix over the same scalar field as A

7.15.3.2 expandout() [1/3]

Expands out.

See also

```
qpp::kron()
```

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

	Α	Eigen expression
	pos	Position
ĺ	dims	Dimensions of the multi-partite system

Returns

Tensor product $I\otimes\cdots\otimes I\otimes A\otimes I\otimes\cdots\otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

```
7.15.3.3 expandout() [2/3]
```

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Note

The std::initializer_list overload exists because otherwise, in the degenerate case when *dims* has only one element, the one element list is implicitly converted to the element's underlying type, i.e. qpp::idx, which has the net effect of picking the wrong (non-vector) qpp::expandout() overload

Parameters

Α	Eigen expression
pos	Position
dims	Dimensions of the multi-partite system

Returns

Tensor product $I\otimes\cdots\otimes I\otimes A\otimes I\otimes\cdots\otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.15.3.4 expandout() [3/3]

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

Α	Eigen expression
pos	Position
n	Number of subsystems
d	Subsystem dimensions

Returns

Tensor product $I \otimes \cdots \otimes I \otimes A \otimes I \otimes \cdots \otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.15.3.5 Fd()

```
cmat qpp::Gates::Fd (
    idx D = 2 ) const [inline]
```

Quantum Fourier transform gate for qudits.

Note

Defined as
$$F = \sum_{j,k=0}^{D-1} \exp(2\pi \mathrm{i} jk/D) |j\rangle\langle k|$$

Parameters

D Dimension of the Hilbert space

Returns

Fourier transform gate for qudits

7.15.3.6 get_name()

Get the name of the most common qubit gates.

Note

Assumes that the gate U is represented by a square matrix. If not, returns the empty string

Parameters

U | Complex matrix representing the quantum gate

Returns

The name of the gate (if any), otherwise the empty string

7.15.3.7 ld()

```
template<typename Derived = Eigen::MatrixXcd>
Derived qpp::Gates::Id (
    idx D = 2 ) const [inline]
```

Identity gate.

Note

Can change the return type from complex matrix (default) by explicitly specifying the template parameter

Parameters

D Dimension of the Hilbert space

Returns

Identity gate on a Hilbert space of dimension D

7.15.3.8 MODMUL()

```
cmat qpp::Gates::MODMUL (
    idx a,
```

```
idx N, idx n) const [inline]
```

Modular multiplication gate for qubits Implements $|x\rangle \longrightarrow |ax \bmod N\rangle$.

Note

For the gate to be unitary, *a* and *N* should be co-prime. The function does not check co-primality in release versions!

The number of qubits required to implement the gate should satisfy $n \geq \lceil \log_2(N) \rceil$

Parameters

а	Positive integer less than N
Ν	Positive integer
n	Number of qubits required for implementing the gate

Returns

Modular multiplication gate

7.15.3.9 Rn()

Qubit rotation of *theta* about the 3-dimensional real (unit) vector *n*.

Parameters

theta	Rotation angle
n	3-dimensional real (unit) vector

Returns

Rotation gate

7.15.3.10 RX()

Qubit rotation of theta about the X axis.

Parameters

theta	Rotation angle
-------	----------------

Returns

Rotation gate

7.15.3.11 RY()

Qubit rotation of *theta* about the Y axis.

Parameters

Returns

Rotation gate

7.15.3.12 RZ()

Qubit rotation of theta about the Z axis.

Parameters

```
theta Rotation angle
```

Returns

Rotation gate

7.15.3.13 SWAPd()

```
cmat qpp::Gates::SWAPd (
        idx D = 2 ) const [inline]
```

SWAP gate for qudits.

Parameters

D Dimension of the Hilbert space

Returns

SWAP gate for qudits

7.15.3.14 Xd()

```
cmat qpp::Gates::Xd (
    idx D = 2 ) const [inline]
```

Generalized X gate for qudits.

Note

```
Defined as X=\sum_{j=0}^{D-1}|j\oplus 1\rangle\langle j|, i.e. raising operator X|j\rangle=|j\oplus 1\rangle
```

Parameters

D Dimension of the Hilbert space

Returns

Generalized X gate for qudits

7.15.3.15 Zd()

```
cmat qpp::Gates::Zd (
    idx D = 2 ) const [inline]
```

Generalized Z gate for qudits.

Note

Defined as
$$Z = \sum_{j=0}^{D-1} \exp(2\pi \mathrm{i} j/D) |j\rangle\langle j|$$

Parameters

D Dimension of the Hilbert space

Returns

Generalized Z gate for qudits

7.15.4 Friends And Related Function Documentation

```
7.15.4.1 internal::Singleton < const Gates >
friend class internal::Singleton < const Gates > [friend]
```

7.15.5 Member Data Documentation

```
7.15.5.1 CNOT
```

```
cmat qpp::Gates::CNOT {cmat::Identity(4, 4)}
```

Controlled-NOT control target gate.

7.15.5.2 CNOTba

```
cmat qpp::Gates::CNOTba {cmat::Zero(4, 4)}
```

Controlled-NOT target->control gate.

7.15.5.3 CZ

```
cmat qpp::Gates::CZ {cmat::Identity(4, 4)}
```

Controlled-Phase gate.

7.15.5.4 FRED

```
cmat qpp::Gates::FRED {cmat::Identity(8, 8)}
```

Fredkin gate.

```
7.15.5.5 H
cmat qpp::Gates::H {cmat::Zero(2, 2)}
Hadamard gate.
7.15.5.6 ld2
cmat qpp::Gates::Id2 {cmat::Identity(2, 2)}
Identity gate.
7.15.5.7 S
cmat qpp::Gates::S {cmat::Zero(2, 2)}
S gate.
7.15.5.8 SWAP
cmat qpp::Gates::SWAP {cmat::Identity(4, 4)}
SWAP gate.
7.15.5.9 T
cmat qpp::Gates::T {cmat::Zero(2, 2)}
T gate.
7.15.5.10 TOF
cmat qpp::Gates::TOF {cmat::Identity(8, 8)}
Toffoli gate.
```

7.15.5.11 X

```
cmat qpp::Gates::X {cmat::Zero(2, 2)}
```

Pauli Sigma-X gate.

7.15.5.12 Y

```
cmat qpp::Gates::Y {cmat::Zero(2, 2)}
```

Pauli Sigma-Y gate.

7.15.5.13 Z

```
cmat qpp::Gates::Z {cmat::Zero(2, 2)}
```

Pauli Sigma-Z gate.

The documentation for this class was generated from the following file:


· classes/gates.h

7.16 qpp::QCircuitDescription::GateStep Struct Reference

One step consisting only of gates/operators in the circuit.

```
#include <classes/circuits.h>
```

 $Collaboration\ diagram\ for\ qpp:: QCircuit Description:: Gate Step:$



Public Member Functions

• GateStep ()=default

Default constructor.

GateStep (GateType gate_type, const cmat &gate, const std::vector< idx > &ctrl, const std::vector< idx > &target, std::string name="")

Constructs a gate step instance.

Public Attributes

```
    GateType gate_type_ = GateType::NONE
        gate type
    cmat gate_
        gate
    std::vector < idx > ctrl_
        control
    std::vector < idx > target_
        target where the gate is applied
    std::string name_
        custom name of the step
```

7.16.1 Detailed Description

One step consisting only of gates/operators in the circuit.

7.16.2 Constructor & Destructor Documentation

Constructs a gate step instance.

Parameters

gate_type	Gate type
gate	Quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes
step_no	Circuit step number
name	Optional gate name

7.16.3 Member Data Documentation

```
7.16.3.1 ctrl_
std::vector<idx> qpp::QCircuitDescription::GateStep::ctrl_
control
7.16.3.2 gate_
cmat qpp::QCircuitDescription::GateStep::gate_
gate
7.16.3.3 gate_type_
GateType qpp::QCircuitDescription::GateStep::gate_type_ = GateType::NONE
gate type
7.16.3.4 name_
std::string qpp::QCircuitDescription::GateStep::name_
```

custom name of the step

7.16.3.5 target_

std::vector<idx> qpp::QCircuitDescription::GateStep::target_

target where the gate is applied

The documentation for this struct was generated from the following file:


· classes/circuits.h

7.17 qpp::IDisplay Class Reference

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

#include <classes/idisplay.h>

Inheritance diagram for qpp::IDisplay:



Public Member Functions

- IDisplay ()=default
 - Default constructor.
- IDisplay (const IDisplay &)=default
 - Default copy constructor.
- IDisplay (IDisplay &&)=default

Default move constructor.

IDisplay & operator= (const IDisplay &)=default

Default copy assignment operator.

• IDisplay & operator= (IDisplay &&)=default

Default move assignment operator.

virtual ∼IDisplay ()=default

Default virtual destructor.

Private Member Functions

virtual std::ostream & display (std::ostream &os) const =0
 Must be overridden by all derived classes.

Friends

std::ostream & operator<< (std::ostream &os, const IDisplay &rhs)
 Overloads the extraction operator.

7.17.1 Detailed Description

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

This class defines friend inline std::ostream& operator<< (std::ostream& os, const qpp::IDisplay& rhs). The latter delegates the work to the pure private virtual function qpp::IDisplay::display() which has to be overridden by all derived classes.

7.17.2 Constructor & Destructor Documentation

```
7.17.2.1 | Display() [1/3]

qpp::IDisplay::IDisplay ( ) [default]

Default constructor.
```

Default copy constructor.

Default move constructor.

```
7.17.2.4 ~|Display()

virtual qpp::IDisplay::~IDisplay ( ) [virtual], [default]
```

Default virtual destructor.

7.17.3 Member Function Documentation

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implemented in qpp::QCircuit, qpp::QCircuitDescription, qpp::QCircuitDescription::iterator::value_type_, qpp::Dynamic_bitset, qpp::internal::IOManipEigen, qpp::Timer< T, CLOCK_T >, qpp::internal::IOManipPointer< PointerType >, and qpp::internal::IOManipRange< InputIterator >.

Default copy assignment operator.

Default move assignment operator.

7.17.4 Friends And Related Function Documentation

7.17.4.1 operator <<

Overloads the extraction operator.

Delegates the work to the virtual function qpp::IDisplay::display()

The documentation for this class was generated from the following file:


· classes/idisplay.h

7.18 qpp::IJSON Class Reference

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

```
#include <classes/idisplay.h>
```

Inheritance diagram for qpp::IJSON:



Public Member Functions

• IJSON ()=default

Default constructor.

• IJSON (const IJSON &)=default

Default copy constructor.

• IJSON (IJSON &&)=default

Default move constructor.

• IJSON & operator= (const IJSON &)=default

Default copy assignment operator.

• IJSON & operator= (IJSON &&)=default

Default move assignment operator.

virtual ∼IJSON ()=default

Default virtual destructor.

virtual std::string to_JSON (bool enclosed_in_curly_brackets=true) const =0

JSON representation of the derived instance, must be overridden by all derived classes.

7.18.1 Detailed Description

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

7.18.2 Constructor & Destructor Documentation

Default constructor.

Default copy constructor.

Default move constructor.

```
7.18.2.4 \simIJSON() virtual qpp::IJSON::\simIJSON ( ) [virtual], [default]
```

Default virtual destructor.

7.18.3 Member Function Documentation

Default copy assignment operator.

Default move assignment operator.

JSON representation of the derived instance, must be overridden by all derived classes.

Parameters

Implemented in qpp::QCircuit, and qpp::QCircuitDescription.

The documentation for this class was generated from the following file:


· classes/idisplay.h

7.19 qpp::Init Class Reference


const Singleton class that performs additional initializations/cleanups

```
#include <classes/init.h>
```

Inheritance diagram for qpp::Init:



Collaboration diagram for qpp::Init:



Private Member Functions

- Init ()
 - Additional initializations.
- ∼Init ()

Cleanups.

Friends

class internal::Singleton < const Init >

Additional Inherited Members

7.19.1 Detailed Description

const Singleton class that performs additional initializations/cleanups

7.19.2 Constructor & Destructor Documentation

```
7.19.2.1 Init()

qpp::Init::Init ( ) [inline], [private]

Additional initializations.
```

```
7.19.2.2 ~ Init()

qpp::Init::~Init ( ) [inline], [private]
```

Cleanups.

7.19.3 Friends And Related Function Documentation

```
7.19.3.1 internal::Singleton < const Init >
friend class internal::Singleton < const Init > [friend]
```

The documentation for this class was generated from the following file:


• classes/init.h

7.20 qpp::exception::InvalidIterator Class Reference


Invalid iterator.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::InvalidIterator:



Collaboration diagram for qpp::exception::InvalidIterator:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.20.1 Detailed Description

Invalid iterator.

7.20.2 Member Function Documentation

7.20.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.20.2.2 type_description()

std::string qpp::exception::InvalidIterator::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

• classes/exception.h


7.21 qpp::internal::IOManipEigen Class Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipEigen:



Collaboration diagram for qpp::internal::IOManipEigen:



Public Member Functions

- template<typename Derived > IOManipEigen (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
- IOManipEigen (const cplx z, double chop=qpp::chop)

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- cmat A_
- double chop_

7.21.1 Constructor & Destructor Documentation

7.21.2 Member Function Documentation

```
7.21.2.1 display()
```

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.21.3 Member Data Documentation

```
7.21.3.1 A_
```

```
cmat qpp::internal::IOManipEigen::A_ [private]
```

7.21.3.2 chop_

double qpp::internal::IOManipEigen::chop_ [private]


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


7.22 qpp::internal::IOManipPointer< PointerType > Class Template Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipPointer< PointerType >:



Collaboration diagram for qpp::internal::IOManipPointer< PointerType >:



Public Member Functions

- IOManipPointer (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")
- IOManipPointer (const IOManipPointer &)=default
- IOManipPointer & operator= (const IOManipPointer &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- const PointerType * p_
- idx N_
- std::string separator_
- std::string start
- std::string end_

7.22.1 Constructor & Destructor Documentation

7.22.1.1 IOManipPointer() [1/2]

7.22.1.2 | IOManipPointer() [2/2]

7.22.2 Member Function Documentation

7.22.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.22.2.2 operator=()

7.22.3 Member Data Documentation

```
7.22.3.1 end_
```

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::end_ [private]
```

7.22.3.2 N_

```
template<typename PointerType>
idx qpp::internal::IOManipPointer< PointerType >::N_ [private]
```

7.22.3.3 p_

```
template<typename PointerType>
const PointerType* qpp::internal::IOManipPointer< PointerType >::p_ [private]
```

7.22.3.4 separator_

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::separator_ [private]
```

7.22.3.5 start

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::start_ [private]
```


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


7.23 qpp::internal::IOManipRange < InputIterator > Class Template Reference

```
#include <internal/classes/iomanip.h>
```

Inheritance diagram for qpp::internal::IOManipRange< InputIterator >:



Collaboration diagram for qpp::internal::IOManipRange< InputIterator >:



Public Member Functions

- IOManipRange (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")
- IOManipRange (const IOManipRange &)=default
- IOManipRange & operator= (const IOManipRange &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- InputIterator first_
- InputIterator last_
- std::string separator_
- std::string start_
- std::string end_

7.23.1 Constructor & Destructor Documentation

7.23.1.1 IOManipRange() [1/2]

7.23.1.2 IOManipRange() [2/2]

7.23.2 Member Function Documentation

7.23.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.23.2.2 operator=()

7.23.3 Member Data Documentation

```
7.23.3.1 end_
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::end_ [private]
7.23.3.2 first_
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::first_ [private]
7.23.3.3 last_
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::last_ [private]
7.23.3.4 separator_
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::separator_ [private]
```

```
7.23.3.5 start_
```

```
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::start_ [private]
```

The documentation for this class was generated from the following file:

• internal/classes/iomanip.h

7.24 qpp::is_complex< T > Struct Template Reference


Checks whether the type is a complex type.

#include <traits.h>

Inheritance diagram for qpp::is_complex< T >:



Collaboration diagram for qpp::is_complex< T >:



7.24.1 Detailed Description

template<typename T> struct qpp::is_complex< T>

Checks whether the type is a complex type.

Provides the constant member *value* which is equal to *true*, if the type is a complex type, i.e. *std::complex<T>*

The documentation for this struct was generated from the following file:

7.25 qpp::is_complex < std::complex < T > > Struct Template Reference


Checks whether the type is a complex number type, specialization for complex types.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_complex < std::complex < T > :



Collaboration diagram for qpp::is_complex< std::complex< T >>:



7.25.1 Detailed Description

```
template<typename T> struct qpp::is_complex< std::complex< T > >
```

Checks whether the type is a complex number type, specialization for complex types.


The documentation for this struct was generated from the following file:

7.26 qpp::is_iterable < T, typename > Struct Template Reference


Checks whether T is compatible with an STL-like iterable container.

#include <traits.h>

Inheritance diagram for qpp::is_iterable < T, typename >:



Collaboration diagram for qpp::is_iterable < T, typename >:



7.26.1 Detailed Description

template<typename T, typename = void> struct qpp::is_iterable< T, typename >

Checks whether T is compatible with an STL-like iterable container.

Provides the constant member *value* which is equal to *true*, if *T* is compatible with an iterable container, i.e. provides at least *begin()* and *end()* member functions and allows de-referencing. Otherwise, *value* is equal to *false*.


The documentation for this struct was generated from the following file:

7.27 qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().begin())) > Struct Template Reference

Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(*(std::declval < T >().begin())) > :



Collaboration diagram for qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std:: \leftarrow :declval< T >().end()), decltype(*(std::declval< T >().begin()))>>:



7.27.1 Detailed Description

 $template < typename \ T > \\ struct \ qpp::is_iterable < T, \ to_void < decltype(std::declval < T > ().begin()), \ decltype(std::declval < T > ().end()), \ decltype(*(std::declval < T > ().begin())) > \\ ::declval < T > ().begin())) > \\$

Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

The documentation for this struct was generated from the following file:

· traits.h

7.28 qpp::is_matrix_expression < Derived > Struct Template Reference


Checks whether the type is an Eigen matrix expression.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_matrix_expression< Derived >:



Collaboration diagram for qpp::is_matrix_expression< Derived >:



7.28.1 Detailed Description

template < typename Derived > struct qpp::is_matrix_expression < Derived >

Checks whether the type is an Eigen matrix expression.

Provides the constant member *value* which is equal to *true*, if the type is an Eigen matrix expression of type *Eigen* :: *MatrixBase* < *Derived* >. Otherwise, *value* is equal to *false*.


The documentation for this struct was generated from the following file:

7.29 qpp::QCircuitDescription::iterator Class Reference

Quantum circuit description bound-checking (safe) iterator.

#include <classes/circuits.h>

Collaboration diagram for qpp::QCircuitDescription::iterator:



Classes

• struct value_type_

Public Types

• using difference_type = long long

iterator trait

• using value_type = value_type_

iterator trait

using pointer = const value_type *

iterator trait

• using reference = const value_type &

iterator trait

• using iterator_category = std::forward_iterator_tag

iterator trait

Public Member Functions

• iterator ()=default

Default constructor.

• iterator (const iterator &)=default

Default copy constructor.

• iterator & operator= (const iterator &)=default

Default copy assignment operator.

• iterator & operator++ ()

Prefix increment operator.

iterator operator++ (int)

Postfix increment operator.

• bool operator== (const iterator &rhs) const

Equality operator.

bool operator!= (iterator rhs) const

Inequality operator.

const value_type_ & operator* () const

Safe de-referencing operator.

void set_begin_ (const QCircuitDescription *qcd)

Sets the iterator to std::begin(this)

void set_end_ (const QCircuitDescription *qcd)

Sets the iterator to std::begin(this)

Private Attributes

```
    const QCircuitDescription * qcd_ {nullptr}
```

< non-owning pointer to const quantum circuit description

value_type_ elem_ {nullptr}

7.29.1 Detailed Description

Quantum circuit description bound-checking (safe) iterator.

Note

The iterator is a const_iterator by default

7.29.2 Member Typedef Documentation

```
7.29.2.1 difference_type
```

```
using qpp::QCircuitDescription::iterator::difference_type = long long
```

iterator trait

7.29.2.2 iterator_category

```
using qpp::QCircuitDescription::iterator::iterator_category = std::forward_iterator_tag
```

iterator trait

7.29.2.3 pointer

```
using qpp::QCircuitDescription::iterator::pointer = const value_type*
```

iterator trait

```
7.29.2.4 reference
```

```
using qpp::QCircuitDescription::iterator::reference = const value_type&
```

iterator trait

```
7.29.2.5 value_type
```

```
using qpp::QCircuitDescription::iterator::value_type = value_type_
```

iterator trait

7.29.3 Constructor & Destructor Documentation

```
7.29.3.1 iterator() [1/2]
```

```
qpp::QCircuitDescription::iterator::iterator ( ) [default]
```

Default constructor.

```
7.29.3.2 iterator() [2/2]
```

Default copy constructor.

7.29.4 Member Function Documentation

```
7.29.4.1 operator"!=()
```

Inequality operator.

Parameters

rhs Iterator against which the inequality is being tested

Returns

True if the iterators are not equal (bit by bit), false otherwise

7.29.4.2 operator*()

```
const value_type_& qpp::QCircuitDescription::iterator::operator* ( ) const [inline]
```

Safe de-referencing operator.

Returns

Constant reference to the iterator element

7.29.4.3 operator++() [1/2]

```
iterator& qpp::QCircuitDescription::iterator::operator++ ( ) [inline]
```

Prefix increment operator.

Returns

Reference to the current instance

7.29.4.4 operator++() [2/2]

Postfix increment operator.

Returns

Copy of the current instance before the increment

```
7.29.4.5 operator=()
```

Default copy assignment operator.

Returns

Reference to the current instance

```
7.29.4.6 operator==()
```

Equality operator.

Parameters

rhs | Iterator against which the equality is being tested

Returns

True if the iterators are equal, false otherwise

```
7.29.4.7 set_begin_()
```

Sets the iterator to std::begin(this)

Parameters

qcd | Constant pointer to a quantum circuit description

```
7.29.4.8 set_end_()
```

Sets the iterator to std::begin(this)

Parameters

qcd Constant pointer to a quantum circuit description

7.29.5 Member Data Documentation

```
7.29.5.1 elem_
```

```
value_type_ qpp::QCircuitDescription::iterator::elem_ {nullptr} [private]
```

7.29.5.2 qcd_

```
const QCircuitDescription* qpp::QCircuitDescription::iterator::qcd_ {nullptr} [private]
```

< non-owning pointer to const quantum circuit description

The documentation for this class was generated from the following file:

classes/circuits.h

7.30 qpp::make_void < Ts > Struct Template Reference

Helper for qpp::to_void<>> alias template.

```
#include <traits.h>
```

Public Types

• typedef void type

7.30.1 Detailed Description

```
template<typename... Ts>
struct qpp::make_void< Ts>
```

Helper for qpp::to_void<>> alias template.

See also

```
qpp::to_void<>
```

7.30.2 Member Typedef Documentation

7.30.2.1 type

```
template<typename... Ts>
typedef void qpp::make_void< Ts >::type
```

The documentation for this struct was generated from the following file:


• traits.h

7.31 qpp::exception::MatrixMismatchSubsys Class Reference


Matrix mismatch subsystems exception.

```
#include <classes/exception.h>
```

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Mismatch Subsys:$



Collaboration diagram for qpp::exception::MatrixMismatchSubsys:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.31.1 Detailed Description

Matrix mismatch subsystems exception.

Matrix size mismatch subsystem sizes (e.g. in qpp::apply())

7.31.2 Member Function Documentation

7.31.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred
-------	--

7.31.2.2 type_description()

std::string qpp::exception::MatrixMismatchSubsys::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.32 qpp::exception::MatrixNotCvector Class Reference


Matrix is not a column vector exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Cvector:$



Collaboration diagram for qpp::exception::MatrixNotCvector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.32.1 Detailed Description

Matrix is not a column vector exception.

Eigen::Matrix is not a column vector

7.32.2 Member Function Documentation

7.32.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred
-------	--

7.32.2.2 type_description()

std::string qpp::exception::MatrixNotCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.33 qpp::exception::MatrixNotRvector Class Reference


Matrix is not a row vector exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Rvector:$



Collaboration diagram for qpp::exception::MatrixNotRvector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.33.1 Detailed Description

Matrix is not a row vector exception.

Eigen::Matrix is not a row vector

7.33.2 Member Function Documentation

7.33.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred
-------	--

7.33.2.2 type_description()

std::string qpp::exception::MatrixNotRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.34 qpp::exception::MatrixNotSquare Class Reference


Matrix is not square exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception::MatrixNotSquare:$



 $Collaboration\ diagram\ for\ qpp::exception::MatrixNotSquare:$



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.34.1 Detailed Description

Matrix is not square exception.

Eigen::Matrix is not a square matrix

7.34.2 Member Function Documentation

7.34.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where Text representing where the exception occurred
--

7.34.2.2 type_description()

std::string qpp::exception::MatrixNotSquare::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.35 qpp::exception::MatrixNotSquareNorCvector Class Reference


Matrix is not square nor column vector exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Square Nor Cvector:$



Collaboration diagram for qpp::exception::MatrixNotSquareNorCvector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.35.1 Detailed Description

Matrix is not square nor column vector exception.

Eigen::Matrix is not a square matrix nor a column vector

7.35.2 Member Function Documentation

7.35.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where Text representing where the exception occ

7.35.2.2 type_description()

std::string qpp::exception::MatrixNotSquareNorCvector::type_description () const [inline],
[override], [virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.36 qpp::exception::MatrixNotSquareNorRvector Class Reference


Matrix is not square nor row vector exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Square Nor Rvector:$



Collaboration diagram for qpp::exception::MatrixNotSquareNorRvector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.36.1 Detailed Description

Matrix is not square nor row vector exception.

Eigen::Matrix is not a square matrix nor a row vector

7.36.2 Member Function Documentation

7.36.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.36.2.2 type_description()

```
std::string qpp::exception::MatrixNotSquareNorRvector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.37 qpp::exception::MatrixNotSquareNorVector Class Reference


Matrix is not square nor vector exception.

```
#include <classes/exception.h>
```

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Square Nor Vector:$



Collaboration diagram for qpp::exception::MatrixNotSquareNorVector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.37.1 Detailed Description

Matrix is not square nor vector exception.

Eigen::Matrix is not a square matrix nor a row/column vector

7.37.2 Member Function Documentation

7.37.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred
-------	--

7.37.2.2 type_description()

std::string qpp::exception::MatrixNotSquareNorVector::type_description () const [inline],
[override], [virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.38 qpp::exception::MatrixNotVector Class Reference


Matrix is not a vector exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception::MatrixNotVector:$



Collaboration diagram for qpp::exception::MatrixNotVector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.38.1 Detailed Description

Matrix is not a vector exception.

Eigen::Matrix is not a row or column vector

7.38.2 Member Function Documentation

7.38.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred
-------	--

7.38.2.2 type_description()

std::string qpp::exception::MatrixNotVector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.39 qpp::QCircuitDescription::MeasureStep Struct Reference

One step consisting only of measurements in the circuit.

```
#include <classes/circuits.h>
```

Collaboration diagram for qpp::QCircuitDescription::MeasureStep:



Public Member Functions

• MeasureStep ()=default

Default constructor.

MeasureStep (MeasureType measurement_type, const std::vector < cmat > &mats, const std::vector < idx > &target, idx c_reg, std::string name="")

Constructs a measurement step instance.

Public Attributes

MeasureType measurement_type_ = MeasureType::NONE

measurement type

- std::vector< cmat > mats_
- std::vector < idx > target

measurement

idx c_reg_ {}

result is being stored

• std::string name_

custom name of the step

7.39.1 Detailed Description

One step consisting only of measurements in the circuit.

7.39.2 Constructor & Destructor Documentation

```
7.39.2.1 MeasureStep() [1/2]

qpp::QCircuitDescription::MeasureStep::MeasureStep ( ) [default]
```

Default constructor.

7.39.2.2 MeasureStep() [2/2]

Constructs a measurement step instance.

Parameters

measurement_type	Measurement type
mats	Vector of measurement matrices (can be only one or many for Kraus measurements)
target	Target qudit indexes
c_reg	Classical register where the value of the measurement is stored
step_no	Circuit step number
name	Optional gate name

7.39.3 Member Data Documentation

```
7.39.3.1 c_reg_
idx qpp::QcircuitDescription::MeasureStep::c_reg_ ()
result is being stored
index of the classical register where the measurement
7.39.3.2 mats_
std::vector<cmat> qpp::QcircuitDescription::MeasureStep::mats_
matrix/matrices that specify the
7.39.3.3 measurement_type_
MeasureType qpp::QcircuitDescription::MeasureStep::measurement_type_ = MeasureType::NONE
measurement type
7.39.3.4 name_
```

std::string qpp::QCircuitDescription::MeasureStep::name_

custom name of the step

7.39.3.5 target_

std::vector<idx> qpp::QCircuitDescription::MeasureStep::target_

measurement

target where the measurement is applied

The documentation for this struct was generated from the following file:


· classes/circuits.h

7.40 qpp::exception::NoCodeword Class Reference


Codeword does not exist exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NoCodeword:



Collaboration diagram for qpp::exception::NoCodeword:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.40.1 Detailed Description

Codeword does not exist exception.

Codeword does not exist, thrown when calling qpp::Codes::codeword() with an invalid index

7.40.2 Member Function Documentation

7.40.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.40.2.2 type_description()

```
std::string qpp::exception::NoCodeword::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.41 qpp::NoiseBase < T > Class Template Reference

Base class for all noise models, derive your particular noise model.

```
#include <classes/noise.h>
```

Collaboration diagram for qpp::NoiseBase< T >:



Public Types

using noise_type = T

Public Member Functions

• template<typename U = noise_type>

NoiseBase (const std::vector< cmat > &Ks, typename std::enable_if< std::is_same< NoiseType::StateDependent, U >::value >::type *=nullptr)

Constructs a noise instance for StateDependent noise type.

• template<typename U = noise_type>

NoiseBase (const std::vector< cmat > &Ks, const std::vector< double > &probs, typename std::enable_if< std::is same< NoiseType::StateIndependent, U >::value >::type *=nullptr)

Constructs a noise instance for StateIndependent noise type.

virtual ∼NoiseBase ()=default

Default virtual destructor.

idx get_d () const noexcept

Qudit dimension.

std::vector< cmat > get_Ks () const

Vector of noise operators.

std::vector< double > get_probs () const

Vector of probabilities corresponding to each noise operator.

• idx get last idx () const

Index of the last occurring noise element.

double get_last_p () const

Probability of the last occurring noise element.

cmat get_last_K () const

Last occurring noise element.

· virtual cmat operator() (const cmat &state, idx target) const

Function invocation operator, applies the underlying noise model on qudit target of the multi-partite state vector or density matrix state.

virtual cmat operator() (const cmat &state, const std::vector < idx > &target) const

Function invocation operator, applies the underlying correlated noise model on qudits specified by target of the multipartite state vector or density matrix state.

Protected Member Functions

void compute_probs_ (const cmat &state, const std::vector < idx > &target) const
 Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

• cmat compute state (const cmat &state, const std::vector < idx > &target) const

Compute the resulting state after the noise was applied.

Protected Attributes

const std::vector< cmat > Ks

Kraus operators.

std::vector< double > probs_

probabilities

• idx d_ {}

qudit dimension

idx i_{}

index of the last occurring noise element

bool generated_ {false}

invoked, or if the noise is state-independent

7.41.1 Detailed Description

```
\label{eq:template} \begin{split} \text{template} &< \text{class T}> \\ \text{class qpp::NoiseBase} &< \text{T}> \end{split}
```

Base class for all noise models, derive your particular noise model.

7.41.2 Member Typedef Documentation

7.41.2.1 noise_type

```
template<class T>
using qpp::NoiseBase< T >::noise_type = T
```

7.41.3 Constructor & Destructor Documentation

7.41.3.1 NoiseBase() [1/2]

Constructs a noise instance for StateDependent noise type.

Note

SFINAEd-out for StateIndependent noise

Parameters

Α	Eigen expression (state vector or density matrix)
Ks	Vector of noise (Kraus) operators that specify the noise
d	Subsystem dimension

7.41.3.2 NoiseBase() [2/2]

template<class T>

Constructs a noise instance for StateIndependent noise type.

Note

SFINAEd-out for StateDependent noise

Parameters

Α	Eigen expression (state vector or density matrix)
Ks	Vector of noise (Kraus) operators that specify the noise
d	Subsystem dimension

7.41.3.3 ∼NoiseBase()

```
template<class T>
virtual qpp::NoiseBase< T >::~NoiseBase ( ) [virtual], [default]
```

Default virtual destructor.

7.41.4 Member Function Documentation

7.41.4.1 compute_probs_()

Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

Parameters

state	State vector or density matrix
target	Qudit indexes where the noise is applied

7.41.4.2 compute_state_()

Compute the resulting state after the noise was applied.

Parameters

state	State vector or density matrix
target	Qudit indexes where the noise is applied

Returns

Resulting state after the noise was applied

7.41.4.3 get_d()

```
template<class T>
idx qpp::NoiseBase< T >::get_d ( ) const [inline], [noexcept]
```

Qudit dimension.

Returns

Qudit dimension

7.41.4.4 get_Ks()

```
template<class T>
std::vector<cmat> qpp::NoiseBase< T >::get_Ks () const [inline]
```

Vector of noise operators.

Returns

Vector of noise operators

```
7.41.4.5 get_last_idx()
```

```
template<class T>
idx qpp::NoiseBase< T >::get_last_idx ( ) const [inline]
```

Index of the last occurring noise element.

Returns

Index of the last occurring noise element

```
7.41.4.6 get_last_K()
```

```
template<class T>
cmat qpp::NoiseBase< T >::get_last_K ( ) const [inline]
```

Last occurring noise element.

Returns

Last occurring noise element

```
7.41.4.7 get_last_p()
```

```
template<class T>
double qpp::NoiseBase< T >::get_last_p ( ) const [inline]
```

Probability of the last occurring noise element.

Returns

Probability of the last occurring noise element

```
7.41.4.8 get_probs()
```

```
template<class T>
std::vector<double> qpp::NoiseBase< T >::get_probs ( ) const [inline]
```

Vector of probabilities corresponding to each noise operator.

Returns

Probability vector

```
7.41.4.9 operator()() [1/2]
```

Function invocation operator, applies the underlying noise model on qudit *target* of the multi-partite state vector or density matrix *state*.

Parameters

state	Multi-partite state vector or density matrix
target	Qudit index where the noise is applied

Returns

Resulting state vector or density matrix

7.41.4.10 operator()() [2/2]

Function invocation operator, applies the underlying correlated noise model on qudits specified by *target* of the multi-partite state vector or density matrix *state*.

Parameters

state	Multi-partite state vector or density matrix
target	Qudit indexes where the correlated noise is applied

Returns

Resulting state vector or density matrix

7.41.5 Member Data Documentation

7.41.5.1 d_

```
template<class T>
idx qpp::NoiseBase< T >::d_ {} [mutable], [protected]
qudit dimension
```

7.41.5.2 generated_

```
template<class T>
bool qpp::NoiseBase< T >::generated_ {false} [mutable], [protected]
```

invoked, or if the noise is state-independent

set to true after compute_state_() is

7.41.5.3 i_

```
template<class T>
idx qpp::NoiseBase< T >::i_ {} [mutable], [protected]
```

index of the last occurring noise element

7.41.5.4 Ks_

```
template<class T>
const std::vector<cmat> qpp::NoiseBase< T >::Ks_ [protected]
```

Kraus operators.

7.41.5.5 probs

```
template<class T>
std::vector<double> qpp::NoiseBase< T >::probs_ [mutable], [protected]
```

probabilities

The documentation for this class was generated from the following file:

• classes/noise.h

7.42 qpp::NoiseType Class Reference

Contains template tags used to specify the noise type.

```
#include <classes/noise.h>
```

Classes

class StateDependent

Template tag, used whenever the noise is state-dependent.

· class StateIndependent

Template tag, used whenever the noise is state-independent.

7.42.1 Detailed Description

Contains template tags used to specify the noise type.

The documentation for this class was generated from the following file:


• classes/noise.h

7.43 qpp::exception::NotBipartite Class Reference


Not bi-partite exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotBipartite:



Collaboration diagram for qpp::exception::NotBipartite:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.43.1 Detailed Description

Not bi-partite exception.

std::vector<idx> of dimensions has size different from 2

7.43.2 Member Function Documentation

7.43.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.43.2.2 type_description()

```
std::string qpp::exception::NotBipartite::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.44 qpp::exception::NotImplemented Class Reference


Code not yet implemented.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotImplemented:



Collaboration diagram for qpp::exception::NotImplemented:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.44.1 Detailed Description

Code not yet implemented.

7.44.2 Member Function Documentation

7.44.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.44.2.2 type_description()

```
std::string qpp::exception::NotImplemented::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.45 qpp::exception::NotQubitCvector Class Reference


Column vector is not 2 x 1 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitCvector:



Collaboration diagram for qpp::exception::NotQubitCvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.45.1 Detailed Description

Column vector is not 2 x 1 exception.

Eigen::Matrix is not 2 x 1

7.45.2 Member Function Documentation

7.45.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.45.2.2 type_description()

std::string qpp::exception::NotQubitCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.46 qpp::exception::NotQubitMatrix Class Reference


Matrix is not 2 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitMatrix:



Collaboration diagram for qpp::exception::NotQubitMatrix:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.46.1 Detailed Description

Matrix is not 2 x 2 exception.

Eigen::Matrix is not 2 x 2

7.46.2 Member Function Documentation

7.46.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.46.2.2 type_description()

std::string qpp::exception::NotQubitMatrix::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.47 qpp::exception::NotQubitRvector Class Reference


Row vector is not 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitRvector:



Collaboration diagram for qpp::exception::NotQubitRvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.47.1 Detailed Description

Row vector is not 1 x 2 exception.

Eigen::Matrix is not 1 x 2

7.47.2 Member Function Documentation

7.47.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.47.2.2 type_description()

std::string qpp::exception::NotQubitRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.48 qpp::exception::NotQubitSubsys Class Reference


Subsystems are not qubits exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitSubsys:



Collaboration diagram for qpp::exception::NotQubitSubsys:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.48.1 Detailed Description

Subsystems are not qubits exception.

Subsystems are not 2-dimensional (qubits)

7.48.2 Member Function Documentation

7.48.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.48.2.2 type_description()

```
std::string qpp::exception::NotQubitSubsys::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.49 qpp::exception::NotQubitVector Class Reference


Vector is not 2 x 1 nor 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitVector:



Collaboration diagram for qpp::exception::NotQubitVector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.49.1 Detailed Description

Vector is not 2 x 1 nor 1 x 2 exception.

Eigen::Matrix is not 2 x 1 nor 1 x 2

7.49.2 Member Function Documentation

7.49.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.49.2.2 type_description()

std::string qpp::exception::NotQubitVector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.50 qpp::exception::OutOfRange Class Reference


Argument out of range exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::OutOfRange:



Collaboration diagram for qpp::exception::OutOfRange:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.50.1 Detailed Description

Argument out of range exception.

Argument out of range

7.50.2 Member Function Documentation

7.50.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.50.2.2 type_description()

```
std::string qpp::exception::OutOfRange::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.51 qpp::exception::PermInvalid Class Reference


Invalid permutation exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermInvalid:



Collaboration diagram for qpp::exception::PermInvalid:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.51.1 Detailed Description

Invalid permutation exception.

std::vector<idx> does note represent a valid permutation

7.51.2 Member Function Documentation

7.51.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.51.2.2 type_description()

```
std::string qpp::exception::PermInvalid::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.52 qpp::exception::PermMismatchDims Class Reference


Permutation mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermMismatchDims:



Collaboration diagram for qpp::exception::PermMismatchDims:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.52.1 Detailed Description

Permutation mismatch dimensions exception.

Size of the std::vector<idx> representing the permutation is different from the size of the std::vector<idx> of dimensions

7.52.2 Member Function Documentation

7.52.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

7.52.2.2 type_description()

```
std::string qpp::exception::PermMismatchDims::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.53 qpp::QCircuit Class Reference


Quantum circuit simulator class.

#include <classes/circuits.h>

Inheritance diagram for qpp::QCircuit:



Collaboration diagram for qpp::QCircuit:



Public Member Functions

QCircuit (const QCircuitDescription &qcd)

Constructs a quantum circuit out of a quantum circuit description.

• QCircuit (QCircuitDescription &&)=delete

Disables rvalue QCircuitDescription.

virtual ∼QCircuit ()=default

Default virtual destructor.

• ket get_psi () const

Underlying quantum state.

ket & get_ref_psi ()

Reference to the underlying quantum state.

std::vector< idx > get_dits () const

Vector with the values of the underlying classical dits.

• idx get_dit (idx i) const

Value of the classical dit at position i.

std::vector< double > get_probs () const

Vector of underlying measurement outcome probabilities.

· idx get measured (idx i) const

Check whether qudit i was already measured.

std::vector< idx > get_measured () const

Vector of already measured gudit indexes.

std::vector< idx > get_not_measured () const

Vector of non-measured qudit indexes.

· const QCircuitDescription & get_circuit_description () const noexcept

Quantum circuit description.

QCircuit & set_dit (idx i, idx value)

Sets the classical dit at position i.

· void reset ()

Resets the quantum circuit.

• std::ostream & display (std::ostream &os) const override

qpp::IDisplay::display() override

void execute (const QCircuitDescription::iterator::value_type &elem)

Executes one step in the quantum circuit.

void execute (const QCircuitDescription::iterator &it)

Executes one step in the quantum circuit.

std::string to_JSON (bool enclosed_in_curly_brackets=true) const override

qpp::IJOSN::to JSON() override

Protected Member Functions

void set_measured_ (idx i)

Marks gudit i as measured then re-label accordingly the remaining non-measured gudits.

std::vector< idx > get_relative_pos_ (std::vector< idx > v)

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

Protected Attributes

const QCircuitDescription & qcd_

quantum circuit description

ket psi_

state vector

std::vector< idx > dits

classical dits

std::vector< double > probs_

measurement probabilities

std::vector< idx > subsys_

7.53.1 Detailed Description

Quantum circuit simulator class.

See also

qpp::QCircuitDescription

7.53.2 Constructor & Destructor Documentation

Constructs a quantum circuit out of a quantum circuit description.

Note

The quantum circuit description must be an Ivalue

See also

qpp::QCircuit(QCircuitDescription&&)

Note

The initial underlying quantum state is set to $|0\rangle^{\otimes n}$

Parameters

```
qcd Quantum circuit description
```

```
7.53.2.2 QCircuit() [2/2]
```

Disables rvalue QCircuitDescription.

```
7.53.2.3 \simQCircuit()
```

```
virtual qpp::QCircuit::~QCircuit ( ) [virtual], [default]
```

Default virtual destructor.

7.53.3 Member Function Documentation

7.53.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the quantum circuit

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

Executes one step in the quantum circuit.

Parameters

```
elem Step to be executed
```

Executes one step in the quantum circuit.

Parameters

it Iterator to the step to be executed

```
7.53.3.4 get_circuit_description()
```

```
const QCircuitDescription& qpp::QCircuit::get_circuit_description ( ) const [inline], [noexcept]
```

Quantum circuit description.

Returns

Quantum circuit description

7.53.3.5 get_dit()

```
idx qpp::QCircuit::get_dit (
        idx i) const [inline]
```

Value of the classical dit at position i.

Parameters

```
i Classical dit index
```

Returns

Value of the classical dit at position i

7.53.3.6 get_dits()

```
std::vector<idx> qpp::QCircuit::get_dits ( ) const [inline]
```

Vector with the values of the underlying classical dits.

Returns

Vector of underlying classical dits

7.53.3.7 get_measured() [1/2]

Check whether qudit *i* was already measured.

Parameters

i Qudit index

Returns

True if qudit i was already measured, false othwewise

```
7.53.3.8 get_measured() [2/2]
std::vector<idx> qpp::QCircuit::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

7.53.3.9 get_not_measured()

```
std::vector<idx> qpp::QCircuit::get_not_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

Returns

Vector of non-measured qudit indexes

7.53.3.10 get_probs()

```
std::vector<double> qpp::QCircuit::get_probs ( ) const [inline]
```

Vector of underlying measurement outcome probabilities.

Note

The probability vector has the same length as the vector of classical dits. If the measurement result is stored at the index c_reg , then the outcome probability is automatically stored at the same index c_reg in the probability vector.

Returns

Vector of underlying measurement outcome probabilities

```
7.53.3.11 get_psi()
```

```
ket qpp::QCircuit::get_psi ( ) const [inline]
```

Underlying quantum state.

Returns

Underlying quantum state

```
7.53.3.12 get_ref_psi()
```

```
ket& qpp::QCircuit::get_ref_psi ( ) [inline]
```

Reference to the underlying quantum state.

Returns

Reference to the underlying quantum state

7.53.3.13 get_relative_pos_()

```
\label{eq:condition} $$ std::vector < idx > qpp::QCircuit::get_relative_pos_ ( std::vector < idx > v ) [inline], [protected]
```

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

Parameters

```
v Qudit index
```

7.53.3.14 reset()

```
void qpp::QCircuit::reset ( ) [inline]
```

Resets the quantum circuit.

Re-initializes everything to zero and sets the initial state to $|0\rangle^{\otimes n}$

7.53.3.15 set_dit()

Sets the classical dit at position i.

Parameters

i	Classical dit index
value	Classical dit value

Returns

Reference to the current instance

7.53.3.16 set_measured_()

Marks qudit *i* as measured then re-label accordingly the remaining non-measured qudits.

Parameters

i Qudit index

7.53.3.17 to_JSON()

qpp::IJOSN::to_JSON() override

Displays the quantum circuit in JSON format

Parameters

enclosed_in_curly_brackets	If true, encloses the result in curly brackets
----------------------------	--

Returns

String containing the JSON representation of the quantum circuit

Implements qpp::IJSON.

7.53.4 Member Data Documentation

```
7.53.4.1 dits_
std::vector<idx> qpp::QCircuit::dits_ [protected]
classical dits
7.53.4.2 probs_
std::vector<double> qpp::QCircuit::probs_ [protected]
measurement probabilities
7.53.4.3 psi_
ket qpp::QCircuit::psi_ [protected]
state vector
7.53.4.4 qcd_
const QCircuitDescription@ qpp::QCircuit::qcd_ [protected]
quantum circuit description
7.53.4.5 subsys_
std::vector<idx> qpp::QCircuit::subsys_ [protected]
keeps track of the measured subsystems, relabel them after measurements
The documentation for this class was generated from the following file:
```


· classes/circuits.h

7.54 qpp::QCircuitDescription Class Reference


Quantum circuit description class.

#include <classes/circuits.h>

Inheritance diagram for qpp::QCircuitDescription:



Collaboration diagram for qpp::QCircuitDescription:



Classes

struct GateStep

One step consisting only of gates/operators in the circuit.

· class iterator

Quantum circuit description bound-checking (safe) iterator.

struct MeasureStep

One step consisting only of measurements in the circuit.

Public Types

enum GateType {

GateType::NONE, GateType::SINGLE, GateType::TWO, GateType::THREE,

GateType::CUSTOM, GateType::FAN, GateType::QFT, GateType::TFQ,

GateType::SINGLE_CTRL_SINGLE_TARGET, GateType::SINGLE_CTRL_MULTIPLE_TARGET, GateType::MULTIPLE_CTR

GateType::MULTIPLE_CTRL_MULTIPLE_TARGET,

GateType::CUSTOM_CTRL, GateType::SINGLE_cCTRL_SINGLE_TARGET, GateType::SINGLE_cCTRL_MULTIPLE_TARGET

GateType::MULTIPLE cCTRL SINGLE TARGET,

GateType::MULTIPLE_cCTRL_MULTIPLE_TARGET, GateType::CUSTOM_cCTRL }

Type of gate being executed in a gate step.

• enum MeasureType { MeasureType::NONE, MeasureType::MEASURE_Z, MeasureType::MEASURE_V, MeasureType::MEASURE_V_MANY }

Type of measurement being executed in a measurement step.

enum StepType { StepType::NONE, StepType::GATE, StepType::MEASUREMENT }

Types of each step in the quantum circuit.

using const iterator = iterator

both iterators are const_iterators

Public Member Functions

· iterator begin ()

Iterator to the first element.

· const iterator begin () const noexcept

Constant iterator to the first element.

· const iterator cbegin () const noexcept

Constant iterator to the first element.

· iterator end ()

Iterator to the next to the last element.

const_iterator end () const noexcept

Constant iterator to the next to the last element.

· const iterator cend () const noexcept

Constant iterator to the next to the last element.

QCircuitDescription (idx nq, idx nc=0, idx d=2, std::string name="")

Constructs a quantum circuit description.

virtual ~QCircuitDescription ()=default

Default virtual destructor.

• idx get_nq () const noexcept

Total number of qudits in the circuit.

• idx get_nc () const noexcept

Total number of classical dits in the circuit.

• idx get_d () const noexcept

Dimension of the comprising qudits.

const std::vector< MeasureStep > & get_measurements () const noexcept

Vector of qpp::QCircuitDescription::MeasureStep.

const std::vector < GateStep > & get_gates () const noexcept

Vector of qpp::QCircuitDescription::GateStep.

• std::string get name () const

Quantum circuit name.

· idx get measured (idx i) const

Check whether gudit i was already measured.

std::vector < idx > get_measured () const

Vector of already measured gudit indexes.

std::vector< idx > get_non_measured () const

Vector of non-measured gudit indexes.

idx get_gate_count () const noexcept

Quantum circuit total gate count.

idx get measurement count () const noexcept

Quantum circuit total measurement count.

• idx get_step_count () const noexcept

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

QCircuitDescription & gate (const cmat &U, idx i, std::string name="")

Applies the single qudit gate U on single qudit i.

QCircuitDescription & gate (const cmat &U, idx i, idx j, std::string name="")

Applies the two qudit gate U on qudits i and j.

QCircuitDescription & gate (const cmat &U, idx i, idx j, idx k, std::string name="")

Applies the three qudit gate U on qudits i, j and k.

QCircuitDescription & gate fan (const cmat &U, const std::vector < idx > &target, std::string name="")

Applies the single qudit gate U on every qudit listed in target.

QCircuitDescription & gate_fan (const cmat &U, const std::initializer_list< idx > &target, std::string name="")

Applies the single qudit gate U on every qudit listed in target.

QCircuitDescription & gate_fan (const cmat &U, std::string name="")

Applies the single qudit gate U on every remaining non-measured qudit.

QCircuitDescription & gate_custom (const cmat &U, const std::vector< idx > &target, std::string name="")

Jointly applies the custom multiple qudit gate U on the qudit indexes specified by target.

QCircuitDescription & QFT (const std::vector < idx > &target, bool swap QPP_UNUSED_=true)

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

 $\bullet \ \ QCircuitDescription \ \& \ TFQ \ (const \ std::vector < idx > \& target, \ bool \ swap \ QPP_UNUSED_=true) \\$

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuitDescription & CTRL (const cmat &U, idx ctrl, idx target, std::string name="")

Applies the single qudit controlled gate U with control qudit ctrl and target qudit target.

QCircuitDescription & CTRL (const cmat &U, idx ctrl, const std::vector < idx > &target, std::string name="")

Applies the single qudit controlled gate U with control qudit ctrl on every qudit listed in target.

QCircuitDescription & CTRL (const cmat &U, const std::vector < idx > &ctrl, idx target, std::string name="")

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on the target qudit target.

QCircuitDescription & CTRL (const cmat &U, const std::vector< idx > &ctrl, const std::vector< idx > &target, std::string name="")

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on every qudit listed in target.

• QCircuitDescription & CTRL_custom (const cmat &U, const std::vector< idx > &ctrl, const std::vector< idx > &target, std::string name="")

Jointly applies the custom multiple-qudit controlled gate U with multiple control qudits listed in ctrl on the qudit indexes

specified by target.

QCircuitDescription & cCTRL (const cmat &U, idx ctrl_dit, idx target, std::string name="")

Applies the single qubit controlled gate U with classical control dit ctrl and target qudit target.

QCircuitDescription & cCTRL (const cmat &U, idx ctrl_dit, const std::vector< idx > &target, std::string name="")

Applies the single qudit controlled gate U with classical control dit ctrl on every qudit listed in target.

QCircuitDescription & cCTRL (const cmat &U, const std::vector< idx > &ctrl_dits, idx target, std::string name="")

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on the target qudit target.

QCircuitDescription & cCTRL (const cmat &U, const std::vector< idx > &ctrl_dits, const std::vector< idx > &target, std::string name="")

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on every qudit listed in target.

QCircuitDescription & cCTRL_custom (const cmat &U, const std::vector < idx > &ctrl_dits, const std::vector < idx > &target, std::string name="")

Jointly applies the custom multiple-qudit controlled gate U with multiple classical control dits listed in ctrl on the qudit indexes specified by target.

QCircuitDescription & measureZ (idx target, idx c_reg, std::string name="")

Measurement of single qudit in the computational basis (Z-basis)

QCircuitDescription & measureV (const cmat &V, idx target, idx c_reg, std::string name="")

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

QCircuitDescription & measureV (const cmat &V, const std::vector< idx > &target, idx c_reg, std::string name="")

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix V

std::ostream & display (std::ostream &os) const override

gpp::IDisplay::display() override

std::string to JSON (bool enclosed in curly brackets=true) const override

qpp::IJOSN::to_JSON() override

Private Attributes

```
    const idx nq
```

number of qudits

const idx nc

number of classical "dits"

· const idx d_

qudit dimension

std::string name_

optional circuit name

std::vector< bool > measured_

keeps track of the measured qudits

std::vector< GateStep > gates_{}{}

gates

std::vector< MeasureStep > measurements_{{}}

measurements

std::vector < StepType > step_types_{}

type of each step

Friends

std::ostream & operator<< (std::ostream &os, const GateType &gate type)

Extraction operator overload for qpp::QCircuitDescription::GateType enum class.

• std::ostream & operator<< (std::ostream &os, const GateStep &gate_step)

Extraction operator overload for qpp::QCircuitDescription::GateStep class.

std::ostream & operator<< (std::ostream &os, const MeasureType &measure_type)

Extraction operator overload for qpp::QCircuitDescription::MeasureType enum class.

std::ostream & operator<< (std::ostream &os, const MeasureStep &measure_step)

Extraction operator overload for qpp::QCircuitDescription::MeasureStep class.

7.54.1 Detailed Description

Quantum circuit description class.

See also

qpp::QCircuit

7.54.2 Member Typedef Documentation

7.54.2.1 const_iterator

```
using qpp::QCircuitDescription::const_iterator = iterator
```

both iterators are const_iterators

7.54.3 Member Enumeration Documentation

7.54.3.1 GateType

```
enum qpp::QCircuitDescription::GateType [strong]
```

Type of gate being executed in a gate step.

Enumerator

NONE	represents no gate
SINGLE	unitary gate on a single qudit
TWO	unitary gate on 2 qudits
THREE	unitary gate on 3 qudits
CUSTOM	custom gate on multiple qudits
FAN	same unitary gate on multiple qudits
QFT	quantum Fourier transform,
TFQ	quantum inverse Fourier transform,
SINGLE_CTRL_SINGLE_TARGET	one control and one target controlled 1 qudit unitary gate with
SINGLE_CTRL_MULTIPLE_TARGET	one control and multiple targets controlled 1 qudit unitary gate with
MULTIPLE_CTRL_SINGLE_TARGET	multiple controls and single target controlled 1 qudit unitary gate with
MULTIPLE_CTRL_MULTIPLE_TARGET	multiple controls and multiple targets controlled 1 qudit unitary gate with
CUSTOM_CTRL	and multiple targets custom controlled gate with multiple controls
SINGLE_cCTRL_SINGLE_TARGET	one classical control and one target controlled 1 qudit unitary gate with
GeneraelNG betygenTRL_MULTIPLE_TARGET	one classical control and multiple targets controlled 1 qudit unitary gate with
MULTIPLE_cCTRL_SINGLE_TARGET	multiple classical controls and single target controlled 1 qudit unitary gate with

7.54.3.2 MeasureType

```
enum qpp::QCircuitDescription::MeasureType [strong]
```

Type of measurement being executed in a measurement step.

Enumerator

NONE	represents no measurement
MEASURE_Z	Z measurement of single qudit.
MEASURE_V	or rank-1 projectors specified by the columns of matrix V measurement of single qudit in the orthonormal basis
MEASURE_V_MANY	basis or rank-1 projectors specified by the columns of matrix \it{V} measurement of multiple qudits in the orthonormal

7.54.3.3 StepType

```
enum qpp::QCircuitDescription::StepType [strong]
```

Types of each step in the quantum circuit.

Enumerator

NONE	represents no step
GATE	quantum gate
MEASUREMENT	measurement

7.54.4 Constructor & Destructor Documentation

7.54.4.1 QCircuitDescription()

```
qpp::QCircuitDescription::QCircuitDescription (
    idx nq,
    idx nc = 0,
    idx d = 2,
    std::string name = "" ) [inline], [explicit]
```

Constructs a quantum circuit description.

Note

The measurement results can only be stored in the classical dits of which number is specified by nc

Parameters

nq	Number of qbits	
nc	Number of classical dits	
d	Subsystem dimensions (optional, default is qubit, i.e. $d = 2$)	
name	Circuit description name (optional)	

7.54.4.2 ~QCircuitDescription()

```
\label{eq:continuit} \mbox{virtual qpp::QCircuitDescription::$\sim$QCircuitDescription () [virtual], [default]$
```

Default virtual destructor.

7.54.5 Member Function Documentation

```
7.54.5.1 begin() [1/2]
```

```
iterator qpp::QCircuitDescription::begin ( ) [inline]
```

Iterator to the first element.

Returns

Iterator to the first element

```
7.54.5.2 begin() [2/2]
```

```
const_iterator qpp::QCircuitDescription::begin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

7.54.5.3 cbegin()

```
const_iterator qpp::QCircuitDescription::cbegin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

Applies the single qubit controlled gate *U* with classical control dit *ctrl* and target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with classical control dit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the
	classical control dits
name	Optional gate name Generated by Doxygen

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.7 cCTRL() [4/4]
```

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the classical control dits
name	Optional gate name

Returns

Reference to the current instance

7.54.5.8 cCTRL_custom()

Jointly applies the custom multiple-qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the qudit indexes specified by *target*.

Parameters

U	Multiple-qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit indexes where the gate U is applied depending on the values of the classical control dits
name	Optional gate name

Returns

Reference to the current instance

7.54.5.9 cend()

```
const_iterator qpp::QCircuitDescription::cend ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

Returns

Constant iterator to the next to the last element

```
7.54.5.10 CTRL() [1/4]
```

Applies the single qudit controlled gate *U* with control qudit *ctrl* and target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with control qudit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.12 CTRL() [3/4]
```

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

7.54.5.14 CTRL_custom()

Jointly applies the custom multiple-qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the qudit indexes specified by *target*.

Parameters

U	Multiple-qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes where the gate U is applied depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

7.54.5.15 display()

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the quantum circuit description

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.54.5.16 end() [1/2]
```

```
iterator qpp::QCircuitDescription::end ( ) [inline]
```

Iterator to the next to the last element.

Returns

Iterator to the next to the last element

```
7.54.5.17 end() [2/2]
```

```
const_iterator qpp::QCircuitDescription::end ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

Returns

Constant iterator to the next to the last element

Applies the single qudit gate *U* on single qudit *i*.

Parameters

U	Single qudit quantum gate
i	Qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the two qudit gate U on qudits i and j.

Parameters

U	Two qudit quantum gate
i	Qudit index
j	Qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the three qudit gate U on qudits i, j and k.

Parameters

U	Three qudit quantum gate
i	Qudit index
j	Qudit index
k	Qudit index
name	Optional gate name

Returns

Reference to the current instance

7.54.5.21 gate_custom()

Jointly applies the custom multiple qudit gate *U* on the qudit indexes specified by *target*.

Parameters

U	Multiple qudit quantum gate
target	Subsystem indexes where the gate <i>U</i> is applied
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.22 gate_fan() [1/3]
```

Applies the single qudit gate *U* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
target	Target qudit indexes; the gate U is applied on every one of them
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.23 gate_fan() [2/3]
```

Applies the single qudit gate *U* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
target	Target qudit indexes; the gate <i>U</i> is applied on every one of them
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.24 gate_fan() [3/3]
```

Applies the single qudit gate U on every remaining non-measured qudit.

Parameters

U	Single qudit quantum gate
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.25 get_d()
idx qpp::QCircuitDescription::get_d ( ) const [inline], [noexcept]
```

Dimension of the comprising qudits.

Returns

Qudit dimension

```
7.54.5.26 get_gate_count()
idx qpp::QCircuitDescription::get_gate_count ( ) const [inline], [noexcept]
```

Returns

Total gate count

Quantum circuit total gate count.

```
7.54.5.27 get_gates()
```

```
\verb|const| std::vector < GateStep> & qpp::QCircuitDescription::get\_gates () const [inline], [noexcept]| \\
```

 $\label{prop:continuous} \textbf{Vector of qpp::QCircuitDescription::GateStep.}$

Returns

Vector of qpp::QCircuitDescription::GateStep

Check whether qudit *i* was already measured.

D					
Pa	ra	m	ല	aı	r۹

i Qudit index

Returns

True if qudit *i* was already measured, false othwewise

```
7.54.5.29 get_measured() [2/2]
```

std::vector<idx> qpp::QCircuitDescription::get_measured () const [inline]

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

7.54.5.30 get_measurement_count()

```
idx qpp::QCircuitDescription::get_measurement_count ( ) const [inline], [noexcept]
```

Quantum circuit total measurement count.

Returns

Total measurement count

7.54.5.31 get_measurements()

 $\verb|const| std::vector<| MeasureStep>& qpp::QCircuitDescription::get_measurements () const [inline], \\[|noexcept|]$

 $\label{lem:continuous} \textbf{Vector of qpp::QCircuitDescription::} \textbf{MeasureStep.}$

Returns

Vector of qpp::QCircuitDescription::MeasureStep

```
7.54.5.32 get_name()
std::string qpp::QCircuitDescription::get_name ( ) const [inline]
Quantum circuit name.
Returns
     Quantum circuit name
7.54.5.33 get_nc()
idx qpp::QCircuitDescription::get_nc ( ) const [inline], [noexcept]
Total number of classical dits in the circuit.
Returns
     Total number of classical dits
7.54.5.34 get_non_measured()
std::vector<idx> qpp::QCircuitDescription::get_non_measured ( ) const [inline]
Vector of non-measured qudit indexes.
Returns
     Vector of non-measured qudit indexes
7.54.5.35 get_nq()
```

```
idx qpp::QCircuitDescription::get_nq ( ) const [inline], [noexcept]
```

Total number of qudits in the circuit.

Returns

Total number of qudits

7.54.5.36 get_step_count()

```
idx qpp::QCircuitDescription::get_step_count ( ) const [inline], [noexcept]
```

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

Returns

Total (gates + measurements) count

7.54.5.37 measureV() [1/2]

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V
target	Qudit index
c_reg	Classical register where the value of the measurement is stored
name	Optional measurement name

Returns

Reference to the current instance

7.54.5.38 measureV() [2/2]

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V	
target	Target qudit indexes that are jointly measured	
c_reg	Classical register where the value of the measurement is stored	
name	Optional measurement name	Generated

Generated by Doxygen

Returns

Reference to the current instance

7.54.5.39 measureZ()

Measurement of single qudit in the computational basis (Z-basis)

Parameters

target	Qudit index
c_reg	Classical register where the value of the measurement is being stored
name	Optional measurement name, default is "Measure Z"

Returns

Reference to the current instance

7.54.5.40 QFT()

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

7.54.5.41 TFQ()

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the inverse quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

7.54.5.42 to_JSON()

qpp::IJOSN::to_JSON() override

Displays the quantum circuit description in JSON format

Parameters

enclosed_in_cu	ırly_brackets	If true, encloses the result in curly brackets
----------------	---------------	--

Returns

String containing the JSON representation of the quantum circuit description

Implements qpp::IJSON.

7.54.6 Friends And Related Function Documentation

 ${\bf Extraction\ operator\ overload\ for\ qpp::} {\bf QCircuit Description::} {\bf GateType\ enum\ class.}$

Parameters

os	Output stream
gate_type	qpp::QCircuitDescription::GateType enum class

Returns

Output stream

Extraction operator overload for qpp::QCircuitDescription::GateStep class.

Parameters

os	Output stream
gate_type	qpp::QCircuitDescription::GateStep class

Returns

Output stream

Extraction operator overload for qpp::QCircuitDescription::MeasureType enum class.

Parameters

os	Output stream
gate_type	qpp::QCircuitDescription::MeasureType enum class

Returns

Output stream

 ${\bf Extraction\ operator\ overload\ for\ qpp::} {\bf QCircuit Description::} {\bf Measure Step\ class.}$

Parameters

os	Output stream
gate_type	qpp::QCircuitDescription::MeasureStep enum class

Returns

Output stream

7.54.7 Member Data Documentation

```
7.54.7.1 d_
const idx qpp::QCircuitDescription::d_ [private]
qudit dimension
```

7.54.7.2 gates_

```
std::vector<GateStep> qpp::QCircuitDescription::gates_ {} [private]
```

gates

7.54.7.3 measured_

```
std::vector<bool> qpp::QCircuitDescription::measured_ [private]
```

keeps track of the measured qudits

7.54.7.4 measurements_

```
std::vector<MeasureStep> qpp::QCircuitDescription::measurements_ {} [private]
```

measurements

```
7.54.7.5 name_
std::string qpp::QCircuitDescription::name_ [private]
optional circuit name
7.54.7.6 nc_
const idx qpp::QCircuitDescription::nc_ [private]
number of classical "dits"
7.54.7.7 nq_
const idx qpp::QCircuitDescription::nq_ [private]
number of qudits
7.54.7.8 step_types_
std::vector<StepType> qpp::QCircuitDescription::step_types_ {} [private]
type of each step
The documentation for this class was generated from the following file:
```

Generated by Doxygen


· classes/circuits.h

7.55 qpp::QubitAmplitudeDampingNoise Class Reference


Qubit amplitude damping noise, as described in Nielsen and Chuang.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitAmplitudeDampingNoise:



Collaboration diagram for qpp::QubitAmplitudeDampingNoise:



Public Member Functions

• QubitAmplitudeDampingNoise (double gamma)

Qubit amplitude damping noise constructor.

Additional Inherited Members

7.55.1 Detailed Description

Qubit amplitude damping noise, as described in Nielsen and Chuang.

7.55.2 Constructor & Destructor Documentation

7.55.2.1 QubitAmplitudeDampingNoise()

Qubit amplitude damping noise constructor.

Parameters

gamma	Amplitude damping probability
-------	-------------------------------

The documentation for this class was generated from the following file:


classes/noise.h

7.56 qpp::QubitBitFlipNoise Class Reference


Qubit bit flip noise.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitBitFlipNoise:



Collaboration diagram for qpp::QubitBitFlipNoise:



Public Member Functions

QubitBitFlipNoise (double p)
 Qubit bit flip noise constructor.

Additional Inherited Members

7.56.1 Detailed Description

Qubit bit flip noise.

7.56.2 Constructor & Destructor Documentation

7.56.2.1 QubitBitFlipNoise()

```
\label{eq:qpp::QubitBitFlipNoise} $$ \operatorname{qpp}::\operatorname{QubitBitFlipNoise} ($$ \operatorname{double} p ) $$ [inline], [explicit]$
```

Qubit bit flip noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.57 qpp::QubitBitPhaseFlipNoise Class Reference


Qubit bit-phase flip (dephasing) noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitBitPhaseFlipNoise:



Collaboration diagram for qpp::QubitBitPhaseFlipNoise:



Public Member Functions

QubitBitPhaseFlipNoise (double p)
 Qubit bit-phase flip noise constructor.

Additional Inherited Members

7.57.1 Detailed Description

Qubit bit-phase flip (dephasing) noise.

7.57.2 Constructor & Destructor Documentation

7.57.2.1 QubitBitPhaseFlipNoise()

```
\label{eq:qpp::QubitBitPhaseFlipNoise::QubitBitPhaseFlipNoise (} \\ \text{double } p \text{ ) } \quad \text{[inline], [explicit]}
```

Qubit bit-phase flip noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


classes/noise.h

7.58 qpp::QubitDepolarizingNoise Class Reference


Qubit depolarizing noise.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitDepolarizingNoise:



Collaboration diagram for qpp::QubitDepolarizingNoise:



Public Member Functions

QubitDepolarizingNoise (double p)
 Qubit depolarizing noise constructor.

Additional Inherited Members

7.58.1 Detailed Description

Qubit depolarizing noise.

7.58.2 Constructor & Destructor Documentation

7.58.2.1 QubitDepolarizingNoise()

```
\label{eq:qpp::QubitDepolarizingNoise::QubitDepolarizingNoise (} $$ double $p$ ) [inline], [explicit]
```

Qubit depolarizing noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.59 qpp::QubitPhaseDampingNoise Class Reference


Qubit phase damping noise, as described in Nielsen and Chuang.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitPhaseDampingNoise:



Collaboration diagram for qpp::QubitPhaseDampingNoise:



Public Member Functions

QubitPhaseDampingNoise (double lambda)
 Qubit phase damping noise constructor.

Additional Inherited Members

7.59.1 Detailed Description

Qubit phase damping noise, as described in Nielsen and Chuang.

7.59.2 Constructor & Destructor Documentation

7.59.2.1 QubitPhaseDampingNoise()

Qubit phase damping noise constructor.

Parameters

The documentation for this class was generated from the following file:


· classes/noise.h

7.60 qpp::QubitPhaseFlipNoise Class Reference


Qubit phase flip (dephasing) noise.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitPhaseFlipNoise:



Collaboration diagram for qpp::QubitPhaseFlipNoise:



Public Member Functions

• QubitPhaseFlipNoise (double p)

Qubit phase flip (dephasing) noise constructor.

Additional Inherited Members

7.60.1 Detailed Description

Qubit phase flip (dephasing) noise.

7.60.2 Constructor & Destructor Documentation

7.60.2.1 QubitPhaseFlipNoise()

Qubit phase flip (dephasing) noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


• classes/noise.h

7.61 qpp::exception::QuditAlreadyMeasured Class Reference


Qudit was already measured exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::QuditAlreadyMeasured:



Collaboration diagram for qpp::exception::QuditAlreadyMeasured:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.61.1 Detailed Description

Qudit was already measured exception.

The qudit was already measured and cannot be measured again

7.61.2 Member Function Documentation

7.61.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurr	ed
--	----

7.61.2.2 type_description()

std::string qpp::exception::QuditAlreadyMeasured::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.62 qpp::QuditDepolarizingNoise Class Reference


Qudit depolarizing noise.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QuditDepolarizingNoise:



Collaboration diagram for qpp::QuditDepolarizingNoise:



Public Member Functions

QuditDepolarizingNoise (double p, idx d)
 Qudit depolarizing noise constructor.

Private Member Functions

std::vector< cmat > fill_Ks_ (idx d) const

Fills the Kraus operator vector.

std::vector< double > fill_probs_ (double p, idx d) const
 Fills the probability vector.

Additional Inherited Members

7.62.1 Detailed Description

Qudit depolarizing noise.

7.62.2 Constructor & Destructor Documentation

7.62.2.1 QuditDepolarizingNoise()

```
qpp::QuditDepolarizingNoise::QuditDepolarizingNoise ( double p,  idx \ d \ ) \ \ [inline], \ [explicit]
```

Qudit depolarizing noise constructor.

Parameters

р	Noise probability
d	Subsystem dimension

7.62.3 Member Function Documentation

Fills the Kraus operator vector.

Parameters

d Qudit dimension

Returns

Vector of Kraus operators representing the depolarizing noise

7.62.3.2 fill_probs_()

Fills the probability vector.

Parameters

р	Probability
d	Qudit dimension

Returns

Probability vector

The documentation for this class was generated from the following file:


• classes/noise.h

7.63 qpp::RandomDevices Class Reference


Singleton class that manages the source of randomness in the library.

#include <classes/random_devices.h>

Inheritance diagram for qpp::RandomDevices:



Collaboration diagram for qpp::RandomDevices:



Public Member Functions

• std::mt19937 & get_prng ()

Returns a reference to the internal PRNG object.

std::istream & load (std::istream &is)

Loads the state of the PRNG from an input stream.

• std::ostream & save (std::ostream &os) const

Saves the state of the PRNG to an output stream.

Private Member Functions

• RandomDevices ()

Initializes and seeds the random number generators.

∼RandomDevices ()=default

Default destructor.

Private Attributes

 std::random_device rd_ used to seed std::mt19937 prng_

std::mt19937 prng_

Mersenne twister random number generator.

Friends

class internal::Singleton < RandomDevices >

Additional Inherited Members

7.63.1 Detailed Description

Singleton class that manages the source of randomness in the library.

Consists of a wrapper around an std::mt19937 Mersenne twister random number generator engine and an std

∴ random_device engine. The latter is used to seed the Mersenne twister.

Warning

This class DOES NOT seed the standard C number generator used by Eigen::Matrix::Random(), since it is not thread safe. Do not use Eigen::Matrix::Random() or functions that depend on the C style random number engine, but use qpp::rand() instead!

7.63.2 Constructor & Destructor Documentation

7.63.2.1 RandomDevices()

```
qpp::RandomDevices::RandomDevices ( ) [inline], [private]
```

Initializes and seeds the random number generators.

7.63.2.2 ~RandomDevices()

```
\verb"qpp::RandomDevices::$\sim$RandomDevices ( ) [private], [default]
```

Default destructor.

7.63.3 Member Function Documentation

```
7.63.3.1 get_prng()
```

```
std::mt19937& qpp::RandomDevices::get_prng ( ) [inline]
```

Returns a reference to the internal PRNG object.

Returns

Reference to the internal PRNG object

7.63.3.2 load()

```
std::istream& qpp::RandomDevices::load (  \texttt{std::istream \& } is \ ) \quad [inline]
```

Loads the state of the PRNG from an input stream.

Parameters

```
is Input stream
```

Returns

The input stream

7.63.3.3 save()

Saves the state of the PRNG to an output stream.

Parameters

os Output stream

Returns

The output stream

7.63.4 Friends And Related Function Documentation

```
7.63.4.1 internal::Singleton < Random Devices >
```

```
friend class internal::Singleton< RandomDevices > [friend]
```

7.63.5 Member Data Documentation

```
7.63.5.1 prng_
```

```
std::mt19937 qpp::RandomDevices::prng_ [private]
```

Mersenne twister random number generator.

```
7.63.5.2 rd_
```

```
std::random_device qpp::RandomDevices::rd_ [private]
```

used to seed std::mt19937 prng_

The documentation for this class was generated from the following file:

• classes/random_devices.h

7.64 qpp::internal::Singleton < T > Class Template Reference

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

```
#include <internal/classes/singleton.h>
```

Static Public Member Functions

- static T & get_instance () noexcept(std::is_nothrow_constructible < T >::value)
- static T & get_thread_local_instance () noexcept(std::is_nothrow_constructible < T >::value)

Protected Member Functions

- Singleton () noexcept=default
- Singleton (const Singleton &)=delete
- Singleton & operator= (const Singleton &)=delete
- virtual ∼Singleton ()=default

7.64.1 Detailed Description

```
\label{template} \begin{tabular}{ll} template < typename T > \\ class & qpp::internal::Singleton < T > \\ \end{tabular}
```

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

To implement a singleton, derive your class from qpp::internal::Singleton, make qpp::internal::Singleton a friend of your class, then declare the constructor and destructor of your class as private. To get an instance, use the static member function qpp::internal::Singleton::get_instance() (qpp::internal::Singleton::get_thread_local_instance()), which returns a reference (thread_local_reference) to your newly created singleton (thread-safe in C++11).

Example:

See also

Code of qpp::Codes, qpp::Gates, qpp::Init, qpp::RandomDevices, qpp::States or qpp.h for real world examples of usage.

7.64.2 Constructor & Destructor Documentation

```
7.64.2.1 Singleton() [1/2]
template<typename T>
qpp::internal::Singleton < T >::Singleton ( ) [protected], [default], [noexcept]
7.64.2.2 Singleton() [2/2]
template<typename T>
qpp::internal::Singleton < T >::Singleton (
            const Singleton< T > \& ) [protected], [delete]
7.64.2.3 ∼Singleton()
template<typename T>
virtual qpp::internal::Singleton < T >::~Singleton ( ) [protected], [virtual], [default]
7.64.3 Member Function Documentation
7.64.3.1 get_instance()
template<typename T>
\texttt{static T\& qpp::internal::Singleton} < \texttt{T} > :: \texttt{get\_instance ()} \quad \texttt{[inline], [static], [noexcept]}
7.64.3.2 get_thread_local_instance()
template < typename T >
static T& qpp::internal::Singleton< T >::get_thread_local_instance ( ) [inline], [static],
[noexcept]
7.64.3.3 operator=()
template<typename T>
Singleton& qpp::internal::Singleton< T >::operator= (
             const Singleton< T > \& ) [protected], [delete]
```

The documentation for this class was generated from the following file:


• internal/classes/singleton.h

7.65 qpp::exception::SizeMismatch Class Reference

Size mismatch exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SizeMismatch:



Collaboration diagram for qpp::exception::SizeMismatch:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.65.1 Detailed Description

Size mismatch exception.

Sizes do not match

7.65.2 Member Function Documentation

7.65.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.65.2.2 type_description()

```
std::string qpp::exception::SizeMismatch::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

7.66 qpp::NoiseType::StateDependent Class Reference

Template tag, used whenever the noise is state-dependent.

#include <classes/noise.h>

7.66.1 Detailed Description

Template tag, used whenever the noise is state-dependent.

The documentation for this class was generated from the following file:

· classes/noise.h

7.67 qpp::NoiseType::StateIndependent Class Reference

Template tag, used whenever the noise is state-independent.

#include <classes/noise.h>

7.67.1 Detailed Description

Template tag, used whenever the noise is state-independent.

The documentation for this class was generated from the following file:


classes/noise.h

7.68 qpp::States Class Reference


const Singleton class that implements most commonly used states

#include <classes/states.h>

Inheritance diagram for qpp::States:



Collaboration diagram for qpp::States:



Public Member Functions

• ket mes (idx d=2) const

Maximally entangled state of 2 qudits.

• ket zero (idx n, idx d=2) const

Zero state of n qudits.

• ket one (idx n, idx d=2) const

One state of n qudits.

• ket jn (idx j, idx n, idx d=2) const

 $|j\rangle^{\otimes n}$ state of n qudits

• ket plus (idx n) const

Plus state of n qubits.

• ket minus (idx n) const

Minus state of n qubits.

Public Attributes

```
    ket x0 {ket::Zero(2)}
```

Pauli Sigma-X 0-eigenstate |+>

ket x1 {ket::Zero(2)}

Pauli Sigma-X 1-eigenstate |->

ket y0 {ket::Zero(2)}

Pauli Sigma-Y 0-eigenstate |y+>

ket y1 {ket::Zero(2)}

Pauli Sigma-Y 1-eigenstate | y->

ket z0 {ket::Zero(2)}

Pauli Sigma-Z 0-eigenstate | 0>

ket z1 {ket::Zero(2)}

Pauli Sigma-Z 1-eigenstate | 1>

cmat px0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

• cmat px1 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.

```
    cmat py0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 0-eigenstate |y+\rangle < y+|.

    cmat py1 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.

    cmat pz0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
• cmat pz1 {cmat::Zero(2, 2)}
      Projector onto the Pauli Sigma-Z 1-eigenstate | 1><1|.
ket b00 {ket::Zero(4)}
      Bell-00 state, as described in Nielsen and Chuang.

    ket b01 {ket::Zero(4)}

      Bell-01 state, as described in Nielsen and Chuang.

    ket b10 {ket::Zero(4)}

      Bell-10 state, as described in Nielsen and Chuang.
ket b11 {ket::Zero(4)}
      Bell-11 state, as described in Nielsen and Chuang.

    cmat pb00 {cmat::Zero(4, 4)}

      Projector onto the Bell-00 state.

    cmat pb01 {cmat::Zero(4, 4)}

      Projector onto the Bell-01 state.

    cmat pb10 {cmat::Zero(4, 4)}

      Projector onto the Bell-10 state.

    cmat pb11 {cmat::Zero(4, 4)}

      Projector onto the Bell-11 state.
ket GHZ {ket::Zero(8)}
      GHZ state.

    ket W {ket::Zero(8)}

      W state.
cmat pGHZ {cmat::Zero(8, 8)}
      Projector onto the GHZ state.
cmat pW {cmat::Zero(8, 8)}
```

Private Member Functions

- States ()
- ∼States ()=default

Default destructor.

Projector onto the W state.

Friends

class internal::Singleton < const States >

Additional Inherited Members

7.68.1 Detailed Description

const Singleton class that implements most commonly used states

7.68.2 Constructor & Destructor Documentation

```
7.68.2.1 States()

qpp::States::States ( ) [inline], [private]

Initialize the states

7.68.2.2 ~States()

qpp::States::~States ( ) [private], [default]
```

7.68.3 Member Function Documentation

```
7.68.3.1 jn()
```

Default destructor.

 $|j\rangle^{\otimes n}$ state of *n* qudits

Parameters

j	Non-negative integer
n	Non-negative integer
d	Subsystem dimensions

Returns

 $|j\rangle^{\otimes n}$ state of *n* qudits

7.68.3.2 mes()

```
ket qpp::States::mes (
idx d = 2 ) const [inline]
```

Maximally entangled state of 2 qudits.

Parameters

d Subsystem dimensions

Returns

Maximally entangled state $\frac{1}{\sqrt{d}} \sum_{j=0}^{d-1} |jj\rangle$ of 2 qudits

7.68.3.3 minus()

```
ket qpp::States::minus (
          idx n ) const [inline]
```

Minus state of n qubits.

Parameters

n Non-negative integer

Returns

Minus state $|-\rangle^{\otimes n}$ of n qubits

7.68.3.4 one()

```
ket qpp::States::one (
        idx n,
        idx d = 2 ) const [inline]
```

One state of *n* qudits.

Parameters

n	Non-negative integer
d	Subsystem dimensions

Returns

One state $|1\rangle^{\otimes n}$ of n qudits

```
7.68.3.5 plus()
```

```
ket qpp::States::plus (
         idx n ) const [inline]
```

Plus state of *n* qubits.

Parameters

```
n Non-negative integer
```

Returns

Plus state $|+\rangle^{\otimes n}$ of n qubits

7.68.3.6 zero()

```
ket qpp::States::zero (
         idx n,
         idx d = 2 ) const [inline]
```

Zero state of *n* qudits.

Parameters

n	Non-negative integer
d	Subsystem dimensions

Returns

Zero state $|0\rangle^{\otimes n}$ of n qudits

7.68.4 Friends And Related Function Documentation

```
7.68.4.1 internal::Singleton < const States >
```

```
friend class internal::Singleton< const States > [friend]
```

7.68.5 Member Data Documentation

```
7.68.5.1 b00
```

```
ket qpp::States::b00 {ket::Zero(4)}
```

Bell-00 state, as described in Nielsen and Chuang.

```
7.68.5.2 b01
```

```
ket qpp::States::b01 {ket::Zero(4)}
```

Bell-01 state, as described in Nielsen and Chuang.

```
7.68.5.3 b10
```

```
ket qpp::States::b10 {ket::Zero(4)}
```

Bell-10 state, as described in Nielsen and Chuang.

7.68.5.4 b11

```
ket qpp::States::b11 {ket::Zero(4)}
```

Bell-11 state, as described in Nielsen and Chuang.

7.68.5.5 GHZ

```
ket qpp::States::GHZ {ket::Zero(8)}
```

GHZ state.

7.68.5.6 pb00

```
cmat qpp::States::pb00 {cmat::Zero(4, 4)}
```

Projector onto the Bell-00 state.

```
7.68.5.7 pb01
cmat qpp::States::pb01 {cmat::Zero(4, 4)}
Projector onto the Bell-01 state.
7.68.5.8 pb10
cmat qpp::States::pb10 {cmat::Zero(4, 4)}
Projector onto the Bell-10 state.
7.68.5.9 pb11
cmat qpp::States::pb11 {cmat::Zero(4, 4)}
Projector onto the Bell-11 state.
7.68.5.10 pGHZ
cmat qpp::States::pGHZ {cmat::Zero(8, 8)}
Projector onto the GHZ state.
7.68.5.11 pW
cmat qpp::States::pW {cmat::Zero(8, 8)}
Projector onto the W state.
7.68.5.12 px0
```

cmat qpp::States::px0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

```
7.68.5.13 px1
cmat qpp::States::px1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.
7.68.5.14 py0
cmat qpp::States::py0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 0-eigenstate |y+>< y+|.
7.68.5.15 py1
cmat qpp::States::py1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.
7.68.5.16 pz0
cmat qpp::States::pz0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
7.68.5.17 pz1
cmat qpp::States::pz1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 1-eigenstate |1><1|.
7.68.5.18 W
ket qpp::States::W {ket::Zero(8)}
```

W state.

```
7.68.5.19 x0
ket qpp::States::x0 {ket::Zero(2)}
Pauli Sigma-X 0-eigenstate |+>
7.68.5.20 x1
ket qpp::States::x1 {ket::Zero(2)}
Pauli Sigma-X 1-eigenstate |->
7.68.5.21 y0
ket qpp::States::y0 {ket::Zero(2)}
Pauli Sigma-Y 0-eigenstate |y+>
7.68.5.22 y1
ket qpp::States::y1 {ket::Zero(2)}
Pauli Sigma-Y 1-eigenstate |y->
7.68.5.23 z0
ket qpp::States::z0 {ket::Zero(2)}
Pauli Sigma-Z 0-eigenstate |0>
7.68.5.24 z1
ket qpp::States::z1 {ket::Zero(2)}
Pauli Sigma-Z 1-eigenstate |1>
The documentation for this class was generated from the following file:
```


· classes/states.h

7.69 qpp::exception::SubsysMismatchDims Class Reference


Subsystems mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SubsysMismatchDims:



Collaboration diagram for qpp::exception::SubsysMismatchDims:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.69.1 Detailed Description

Subsystems mismatch dimensions exception.

std::vector<idx> of subsystem labels has duplicates, or has entries that are larger than the size of the std← ::vector<idx> of dimensions

7.69.2 Member Function Documentation

7.69.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred
--

7.69.2.2 type_description()

```
std::string qpp::exception::SubsysMismatchDims::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.70 qpp::Timer < T, CLOCK_T > Class Template Reference


Chronometer.

#include <classes/timer.h>

Inheritance diagram for qpp::Timer< T, CLOCK_T >:



Collaboration diagram for qpp::Timer < T, CLOCK_T >:



Public Member Functions

· Timer () noexcept

Constructs an instance with the current time as the starting point.

• void tic () noexcept

Resets the chronometer.

• const Timer & toc () noexcept

Stops the chronometer.

• double tics () const noexcept

Time passed in the duration specified by T.

• template<typename U = T>

U get_duration () const noexcept

Duration specified by U.

• Timer (const Timer &)=default

Default copy constructor.

• Timer (Timer &&)=default

Default move constructor.

• Timer & operator= (const Timer &)=default

Default copy assignment operator.

• Timer & operator= (Timer &&)=default

Default move assignment operator.

virtual ∼Timer ()=default

Default virtual destructor.

Protected Attributes

- CLOCK_T::time_point start_
- CLOCK_T::time_point end_

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display() override*

7.70.1 Detailed Description

```
template < typename\ T = std::chrono::duration < double >, typename\ CLOCK\_T = std::chrono::steady\_clock > class\ qpp::Timer < T,\ CLOCK\_T >
```

Chronometer.

Template Parameters

T	Tics duration, default is std::chrono::duration <double, 1="">, i.e. seconds in double precision</double,>
CLOCK← T	Clock's type, default is std::chrono::steady_clock, not affected by wall clock changes during runtime

7.70.2 Constructor & Destructor Documentation

```
7.70.2.1 Timer() [1/3]
```

```
\label{template} $$ \ensuremath{\texttt{template}}$ $$ \ensuremath{\texttt{typename T = std::chrono::steady}}$ $$ $$ \ensuremath{\texttt{clock}}$ $$ \ensuremath{\texttt{clock}}$ $$ $$ \ensuremath{\texttt{qpp::Timer}}$ $$ \ensuremath{\texttt{T, CLOCK\_T >::Timer}}$ $$ ( ) $$ [inline], [noexcept] $$
```

Constructs an instance with the current time as the starting point.

7.70.2.2 Timer() [2/3]

Default copy constructor.

```
7.70.2.3 Timer() [3/3]
```

Default move constructor.

7.70.2.4 \sim Timer()

```
\label{template} $$ \ensuremath{\sf template}$ $$ \ensurem
```

Default virtual destructor.

7.70.3 Member Function Documentation

7.70.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream the number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc().

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.70.3.2 get_duration()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady 
_clock>
template<typename U = T>
U qpp::Timer< T, CLOCK_T >::get_duration ( ) const [inline], [noexcept]
```

Duration specified by U.

Template Parameters

U Duration, default is T, which defaults to std::chrono::duration<double, 1>, i.e. seconds in double precision

Returns

Duration that passed between the instantiation/reset and invocation of qpp::Timer::toc()

7.70.3.3 operator=() [1/2]

Default copy assignment operator.

7.70.3.4 operator=() [2/2]

Default move assignment operator.

7.70.3.5 tic()

```
 \begin{tabular}{ll} template < type name T = std::chrono::duration < double>, type name CLOCK_T = std::chrono::steady & clock> \\ void qpp::Timer < T, CLOCK_T >::tic ( ) [inline], [noexcept] \\ \end{tabular}
```

Resets the chronometer.

Resets the starting/ending point to the current time

7.70.3.6 tics()

```
 \begin{tabular}{ll} template < typename T = std::chrono::duration < double >, typename CLOCK_T = std::chrono::steady \leftarrow \_clock > \\ double qpp::Timer < T, CLOCK_T >::tics ( ) const [inline], [noexcept] \\ \end{tabular}
```

Time passed in the duration specified by T.

Returns

Number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc()

7.70.3.7 toc()

```
 \begin{tabular}{ll} template < type name $T = std::chrono::steady \leftarrow \_clock > \\ const $Timer\& $qpp::Timer < T, $CLOCK_T > ::toc ( ) [inline], [noexcept] \end{tabular}
```

Stops the chronometer.

Set the current time as the ending point

Returns

Reference to the current instance

7.70.4 Member Data Documentation

7.70.4.1 end

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady←
   _clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::end_ [protected]
```

7.70.4.2 start_

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::start_ [protected]
```

The documentation for this class was generated from the following file:


· classes/timer.h

7.71 qpp::exception::TypeMismatch Class Reference


Type mismatch exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::TypeMismatch:



Collaboration diagram for qpp::exception::TypeMismatch:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.71.1 Detailed Description

Type mismatch exception.

Scalar types do not match

7.71.2 Member Function Documentation

7.71.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred	
-------	--	--

7.71.2.2 type_description()

std::string qpp::exception::TypeMismatch::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.72 qpp::exception::UndefinedType Class Reference


Not defined for this type exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::UndefinedType:



Collaboration diagram for qpp::exception::UndefinedType:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.72.1 Detailed Description

Not defined for this type exception.

Templated specialization is not defined for this type

7.72.2 Member Function Documentation

7.72.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.72.2.2 type_description()

std::string qpp::exception::UndefinedType::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.73 qpp::exception::Unknown Class Reference


Unknown exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Unknown:



Collaboration diagram for qpp::exception::Unknown:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.73.1 Detailed Description

Unknown exception.

Thrown when no other exception is suitable (not recommended, it is better to define another suitable exception type)

7.73.2 Member Function Documentation

7.73.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occ	urred
---	-------

7.73.2.2 type_description()

std::string qpp::exception::Unknown::type_description () const [inline], [override], [virtual]
Exception type description.

Returns

Exception type description


Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.74 qpp::QCircuitDescription::iterator::value_type_ Struct Reference

Inheritance diagram for qpp::QCircuitDescription::iterator::value_type_:



 $Collaboration\ diagram\ for\ qpp:: QCircuit Description:: iterator:: value_type_:$



Public Member Functions

```
    value_type_ (const QCircuitDescription *value_type_qcd)
        Default value_type_ constructor.
    value_type_ (const value_type_ &)=default
        Default copy constructor.
    value_type_ & operator= (const value_type_ &)=default
        Default copy assignment operator.
    std::ostream & display (std::ostream &os) const override
        qpp::IDisplay::display() override
```

Public Attributes

```
• const QCircuitDescription * value_type_qcd_

< non-owning pointer to the parent iterator
```

StepType type_{StepType::NONE}

step type

idx ip_ {idx_infty}

instruction pointer

std::vector < GateStep >::const_iterator gates_ip_ {}
 gates instruction pointer

 $\bullet \ \, \mathsf{std} :: \mathsf{vector} < \mathsf{MeasureStep} > :: \mathsf{const_iterator} \ \, \mathsf{measurements_ip} _ \{ \} \\$

measurements instruction pointer

7.74.1 Constructor & Destructor Documentation

. .

Parameters

```
value_type_qcd Constant pointer to quantum circuit description
```

Default copy constructor.

7.74.2 Member Function Documentation

7.74.2.1 display()

qpp::IDisplay::display() override

Writes to the output stream the textual representation of the iterator de-referenced element

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.74.2.2 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

7.74.3 Member Data Documentation

```
7.74.3.1 gates_ip_
```

```
std::vector<GateStep>::const_iterator qpp::QCircuitDescription::iterator::value_type_::gates
_ip_ {}
```

gates instruction pointer

```
7.74.3.2 ip_
idx qpp::QCircuitDescription::iterator::value_type_::ip_ {idx_infty}
instruction pointer
7.74.3.3 measurements_ip_
std::vector<MeasureStep>::const_iterator qpp::QCircuitDescription::iterator::value_type_←
::measurements_ip_ {}
measurements instruction pointer
7.74.3.4 type_
StepType qpp::QCircuitDescription::iterator::value_type_::type_ {StepType::NONE}
step type
7.74.3.5 value_type_qcd_
const QCircuitDescription* qpp::QCircuitDescription::iterator::value_type_::value_type_qcd_
< non-owning pointer to the parent iterator
The documentation for this struct was generated from the following file:


    classes/circuits.h
```

7.75 qpp::exception::ZeroSize Class Reference


Object has zero size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::ZeroSize:



Collaboration diagram for qpp::exception::ZeroSize:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.75.1 Detailed Description

Object has zero size exception.

Zero sized object, e.g. empty Eigen::Matrix or std::vector with no elements

7.75.2 Member Function Documentation

7.75.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.75.2.2 type_description()

std::string qpp::exception::ZeroSize::type_description () const [inline], [override], [virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h


Chapter 8

File Documentation

8.1 classes/circuits.h File Reference

Support for qudit quantum circuits.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::QCircuitDescription

Quantum circuit description class.

• struct qpp::QCircuitDescription::GateStep

One step consisting only of gates/operators in the circuit.

• struct qpp::QCircuitDescription::MeasureStep

One step consisting only of measurements in the circuit.

• class qpp::QCircuitDescription::iterator

Quantum circuit description bound-checking (safe) iterator.

- struct qpp::QCircuitDescription::iterator::value_type_
- class qpp::QCircuit

Quantum circuit simulator class.

354 File Documentation

Namespaces

• qpp

Quantum++ main namespace.


8.1.1 Detailed Description

Support for qudit quantum circuits.

8.2 classes/codes.h File Reference

Quantum error correcting codes.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::Codes

const Singleton class that defines quantum error correcting codes

Namespaces

• qpp

Quantum++ main namespace.


8.2.1 Detailed Description

Quantum error correcting codes.

8.3 classes/exception.h File Reference

Exceptions.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::exception::Exception

Base class for generating Quantum++ custom exceptions.

· class qpp::exception::Unknown

Unknown exception.

class qpp::exception::ZeroSize

Object has zero size exception.

• class qpp::exception::MatrixNotSquare

Matrix is not square exception.

class qpp::exception::MatrixNotCvector

Matrix is not a column vector exception.

· class qpp::exception::MatrixNotRvector

Matrix is not a row vector exception.

class qpp::exception::MatrixNotVector

Matrix is not a vector exception.

class qpp::exception::MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

• class qpp::exception::MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

· class qpp::exception::MatrixNotSquareNorVector

Matrix is not square nor vector exception.

class qpp::exception::MatrixMismatchSubsys

Matrix mismatch subsystems exception.

· class qpp::exception::DimsInvalid

Invalid dimension(s) exception.

class qpp::exception::DimsNotEqual

Dimensions not equal exception.

class qpp::exception::DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

class qpp::exception::DimsMismatchCvector

356 File Documentation

Dimension(s) mismatch column vector size exception.

· class qpp::exception::DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

· class qpp::exception::DimsMismatchVector

Dimension(s) mismatch vector size exception.

class qpp::exception::SubsysMismatchDims

Subsystems mismatch dimensions exception.

· class qpp::exception::PermInvalid

Invalid permutation exception.

class qpp::exception::PermMismatchDims

Permutation mismatch dimensions exception.

· class qpp::exception::NotQubitMatrix

Matrix is not 2 x 2 exception.

class qpp::exception::NotQubitCvector

Column vector is not 2 x 1 exception.

· class qpp::exception::NotQubitRvector

Row vector is not 1 x 2 exception.

· class qpp::exception::NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

• class qpp::exception::NotQubitSubsys

Subsystems are not qubits exception.

class gpp::exception::NotBipartite

Not bi-partite exception.

· class qpp::exception::NoCodeword

Codeword does not exist exception.

· class qpp::exception::OutOfRange

Argument out of range exception.

· class qpp::exception::TypeMismatch

Type mismatch exception.

class qpp::exception::SizeMismatch

Size mismatch exception.

class qpp::exception::UndefinedType

Not defined for this type exception.

· class qpp::exception::QuditAlreadyMeasured

Qudit was already measured exception.

· class qpp::exception::Duplicates

System (e.g. std::vector) has duplicates exception.

· class qpp::exception::CustomException

Custom exception.

· class qpp::exception::NotImplemented

Code not yet implemented.

· class qpp::exception::InvalidIterator

Invalid iterator.

Namespaces

qpp

Quantum++ main namespace.

qpp::exception

Quantum++ exception hierarchy namespace.


8.3.1 Detailed Description

Exceptions.

8.4 classes/gates.h File Reference

Quantum gates.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::Gates

const Singleton class that implements most commonly used gates

Namespaces

• qpp

Quantum++ main namespace.

8.4.1 Detailed Description


Quantum gates.

358 File Documentation

8.5 classes/idisplay.h File Reference

Display interface via the non-virtual interface (NVI) and very basic JSON serialization support interface.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

class qpp::IJSON

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

Namespaces

• qpp

Quantum++ main namespace.


8.5.1 Detailed Description

Display interface via the non-virtual interface (NVI) and very basic JSON serialization support interface.

8.6 classes/init.h File Reference

Initialization.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::Init

const Singleton class that performs additional initializations/cleanups

Namespaces

• qpp

Quantum++ main namespace.


8.6.1 Detailed Description

Initialization.

8.7 classes/noise.h File Reference

Noise models.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::NoiseType

Contains template tags used to specify the noise type.

class qpp::NoiseBase< T >

Base class for all noise models, derive your particular noise model.

class qpp::QubitDepolarizingNoise

Qubit depolarizing noise.

· class qpp::QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

• class qpp::QubitBitFlipNoise

Qubit bit flip noise.

· class qpp::QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

· class qpp::QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

· class qpp::QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

· class qpp::QuditDepolarizingNoise

Qudit depolarizing noise.

360 File Documentation

Namespaces

• qpp

Quantum++ main namespace.


8.7.1 Detailed Description

Noise models.

8.8 classes/random_devices.h File Reference

Random devices.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::RandomDevices

Singleton class that manages the source of randomness in the library.

Namespaces

• qpp

Quantum++ main namespace.


8.8.1 Detailed Description

Random devices.

8.9 classes/reversible.h File Reference

Support for classical reversible circuits.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::Dynamic_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

class qpp::Bit_circuit

Classical reversible circuit simulator.

• struct qpp::Bit_circuit::Gate_count

Namespaces

qpp

Quantum++ main namespace.


8.9.1 Detailed Description

Support for classical reversible circuits.

8.10 classes/states.h File Reference

Quantum states.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::States

const Singleton class that implements most commonly used states

Namespaces

• qpp

Quantum++ main namespace.


8.10.1 Detailed Description

Quantum states.

8.11 classes/timer.h File Reference

Timing.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::Timer < T, CLOCK_T >
 Chronometer.

Namespaces

• qpp

Quantum++ main namespace.


8.11.1 Detailed Description

Timing.

8.12 constants.h File Reference

Constants.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

• qpp::literals

Functions

- constexpr cplx qpp::literals::operator"" _i (unsigned long long int x) noexcept
- $\textit{User-defined literal for complex } i = \sqrt{-1} \; \textit{(integer overload)} \\ \bullet \; \textit{constexpr cplx qpp::operator} \\ \text{"} \; \underline{-i} \; \textit{(long double x) noexcept} \\$

User-defined literal for complex $i = \sqrt{-1}$ (real overload)

• cplx qpp::omega (idx D)

D-th root of unity.

Variables

• constexpr double qpp::chop = 1e-10

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

constexpr double qpp::eps = std::numeric_limits<double>::epsilon()

Used to decide whether a number or expression in double precision is zero or not for the purpose of a specific computation.

• constexpr idx qpp::maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

• constexpr double qpp::pi = 3.141592653589793238462643383279502884

• constexpr double qpp::ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

constexpr double qpp::infty = std::numeric_limits<double>::max()

Used to denote infinity in double precision.

• const idx qpp::idx_infty = static_cast<idx>(-1)

Used to denote the largest unsigned index.


8.12.1 Detailed Description

Constants.

8.13 entanglement.h File Reference

Entanglement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

```
template<typename Derived >
  dyn col vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector<
  idx > &dims)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  dyn_col_vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  cmat qpp::schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat qpp::schmidtA (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Bob side.
template<typename Derived >
  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Bob side.
• template<typename Derived >
  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx
  > &dims)
      Schmidt probabilities of the bi-partite pure state A.

    template<typename Derived >

  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt probabilities of the bi-partite pure state A.
• template<typename Derived >
  double qpp::entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Entanglement of the bi-partite pure state A.
• template<typename Derived >
  double <a href="mailto:qpp::entanglement">qpp::entanglement</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Entanglement of the bi-partite pure state A.

    template<typename Derived >

  double <a href="mailto:qpp::gconcurrence">qpp::gconcurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      G-concurrence of the bi-partite pure state A.

    template<typename Derived >

  double qpp::negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double <a href="mailto:qpp::negativity">qpp::negativity</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double <a href="mailto:qpp::concurrence">qpp::concurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.
```


8.13.1 Detailed Description

Entanglement functions.

8.14 entropies.h File Reference

Entropy functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

```
    template < typename Derived >
        double qpp::entropy (const Eigen::MatrixBase < Derived > &A)
```

von-Neumann entropy of the density matrix A

double qpp::entropy (const std::vector< double > &prob)

Shannon entropy of the probability distribution prob.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

```
double <a href="mailto:qpp::renyi">qpp::renyi</a> (const Eigen::MatrixBase< Derived > &A, double alpha)
```

Renyi- α entropy of the density matrix A, for $\alpha \geq 0$.

double qpp::renyi (const std::vector< double > &prob, double alpha)

Renyi- α entropy of the probability distribution prob, for $\alpha \geq 0.$

• template<typename Derived >

```
double <a href="mailto:qpp::tsallis">qpp::tsallis</a> (const Eigen::MatrixBase< Derived > &A, double q)
```

Tsallis- q entropy of the density matrix A, for $q \geq 0$.

double qpp::tsallis (const std::vector< double > &prob, double q)

Tsallis- q entropy of the probability distribution prob, for $q \geq 0$.

• template<typename Derived >

double qpp::qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const std::vector< idx > &subsysB, const std::vector< idx > &dims)

Quantum mutual information between 2 subsystems of a composite system.

• template<typename Derived >

 $\label{lem:double qpp::qmutualinfo} $$ double qpp::qmutualinfo (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &subsysA, const std::vector < idx > &subsysB, idx d=2) \\$

Quantum mutual information between 2 subsystems of a composite system.

8.14.1 Detailed Description

Entropy functions.

8.15 experimental/experimental.h File Reference

Experimental/test functions/classes.

Namespaces

• qpp

Quantum++ main namespace.

· qpp::experimental

Experimental/test functions/classes, do not use or modify.


8.15.1 Detailed Description

Experimental/test functions/classes.

8.16 functions.h File Reference

Generic quantum computing functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

· qpp::literals

Functions

```
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::transpose (const Eigen::MatrixBase< Derived > &A)
• template<typename Derived >
  dyn mat< typename Derived::Scalar > qpp::conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::adjoint (const Eigen::MatrixBase< Derived > &A)
      Adjoint.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::inverse (const Eigen::MatrixBase< Derived > &A)
      Inverse.

    template<typename Derived >

  Derived::Scalar qpp::trace (const Eigen::MatrixBase < Derived > &A)
• template<typename Derived >
  Derived::Scalar <a href="mailto:qpp::det">qpp::det</a> (const Eigen::MatrixBase</a> Derived > &A)

    template<typename Derived >

  Derived::Scalar qpp::logdet (const Eigen::MatrixBase< Derived > &A)
     Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar <a href="mailto:qpp::sum">qpp::sum</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise sum of A.
template<typename Derived >
  Derived::Scalar <a href="mailto:open:prod">open:prod</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise product of A.

    template<typename Derived >

  double <a href="mailto:qpp::norm">qpp::norm</a> (const Eigen::MatrixBase< Derived > &A)
      Frobenius norm.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::normalize (const Eigen::MatrixBase< Derived > &A)
      Normalizes state vector (column or row vector) or density matrix.
• template<typename Derived >
  std::pair< dyn_col_vect< cplx >, cmat > qpp::eig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition.
• template<typename Derived >
  dyn_col_vect< cplx > qpp::evals (const Eigen::MatrixBase< Derived > &A)
     Eigenvalues.

    template<typename Derived >

  cmat qpp::evects (const Eigen::MatrixBase< Derived > &A)
      Eigenvectors.

    template<typename Derived >

  std::pair< dyn_col_vect< double >, cmat > qpp::heig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > qpp::hevals (const Eigen::MatrixBase< Derived > &A)
      Hermitian eigenvalues.
• template<typename Derived >
  cmat qpp::hevects (const Eigen::MatrixBase< Derived > &A)
      Eigenvectors of Hermitian matrix.
```

```
• template<typename Derived >
  std::tuple< cmat, dyn_col_vect< double >, cmat > qpp::svd (const Eigen::MatrixBase< Derived > &A)
     Full singular value decomposition.

    template<typename Derived >

  dyn_col_vect< double > qpp::svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.
• template<typename Derived >
  cmat qpp::svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.

    template<typename Derived >

  cmat qpp::svdV (const Eigen::MatrixBase< Derived > &A)
     Right singular vectors.

    template<typename Derived >

  cmat qpp::funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)

    template < typename Derived >

  cmat qpp::sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.
• template<typename Derived >
  cmat qpp::absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.

    template<typename Derived >

  cmat qpp::expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.
• template<typename Derived >
  cmat qpp::logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.
• template<typename Derived >
  cmat <a href="mailto:qpp::sinm">qpp::sinm</a> (const Eigen::MatrixBase</a> Derived > &A)
     Matrix sin.
• template<typename Derived >
  cmat qpp::cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.
• template<typename Derived >
  cmat qpp::spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.
template<typename Derived >
  dyn mat< typename Derived::Scalar > qpp::powm (const Eigen::MatrixBase< Derived > &A, idx n)
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

    template<typename Derived >

  double qpp::schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > qpp::cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const
  typename Derived::Scalar &))
     Functor.

    template<typename T >

  dyn_mat< typename T::Scalar > qpp::kron (const T &head)
     Kronecker product.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > qpp::kron (const T &head, const Args &... tail)
     Kronecker product.
```

```
    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::kron (const std::vector< Derived > &As)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::kron (const std::initializer list< Derived > &As)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Kronecker power.
• template<typename T >
  dyn_mat< typename T::Scalar > qpp::dirsum (const T &head)
     Direct sum.
• template<typename T , typename... Args>
  dyn mat< typename T::Scalar > qpp::dirsum (const T &head, const Args &... tail)
     Direct sum.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::vector< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::initializer_list< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::reshape (const Eigen::MatrixBase< Derived > &A, idx rows,
  idx cols)
     Reshape.

    template < typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > qpp::comm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Commutator.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > qpp::anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::prj (const Eigen::MatrixBase< Derived > &A)
     Projector.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::grams (const std::vector< Derived > &As)
     Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::grams (const std::initializer list< Derived > &As)
     Gram-Schmidt orthogonalization.
• template<typename Derived >
  dyn mat< typename Derived::Scalar > qpp::grams (const Eigen::MatrixBase< Derived > &A)
     Gram-Schmidt orthogonalization.

    std::vector< idx > qpp::n2multiidx (idx n, const std::vector< idx > &dims)

     Non-negative integer index to multi-index.

    idx qpp::multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

     Multi-index to non-negative integer index.
```

ket qpp::mket (const std::vector< idx > &mask, const std::vector< idx > &dims)

Multi-partite qudit ket.

ket qpp::mket (const std::vector< idx > &mask, idx d=2)

Multi-partite qudit ket.

cmat qpp::mprj (const std::vector< idx > &mask, const std::vector< idx > &dims)

Projector onto multi-partite qudit ket.

cmat qpp::mprj (const std::vector< idx > &mask, idx d=2)

Projector onto multi-partite qudit ket.

template<typename InputIterator >

```
std::vector< double > qpp::abssq (InputIterator first, InputIterator last)
```

Computes the absolute values squared of an STL-like range of complex numbers.

• template<typename Container >

```
std::vector< double > qpp::abssq (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)
```

Computes the absolute values squared of an STL-like container.

template<typename Derived >

```
std::vector< double > qpp::abssq (const Eigen::MatrixBase< Derived > &A)
```

Computes the absolute values squared of an Eigen expression.

• template<typename InputIterator >

```
std::iterator_traits< InputIterator >::value_type qpp::sum (InputIterator first, InputIterator last)
```

Element-wise sum of an STL-like range.

template<typename Container >

```
Container::value_type qpp::sum (const Container &c, typename std::enable_if< is_iterable< Container >
::value >::type *=nullptr)
```

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

```
std::iterator_traits< InputIterator >::value_type qpp::prod (InputIterator first, InputIterator last)
```

Element-wise product of an STL-like range.

template<typename Container >

```
Container::value_type qpp::prod (const Container &c, typename std::enable_if< is_iterable< Container >
::value >::type *=nullptr)
```

Element-wise product of the elements of an STL-like container.

• template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > qpp::rho2pure (const Eigen::MatrixBase< Derived > &A)
```

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

• std::vector< idx > qpp::complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

```
std::vector< double > qpp::rho2bloch (const Eigen::MatrixBase< Derived > &A)
```

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat qpp::bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

template<char... Bits>

```
ket qpp::literals::operator"" _ket ()
```

Multi-partite qubit ket user-defined literal.

• template<char... Bits>

```
bra qpp::literals::operator"" _bra ()
```

Multi-partite qubit bra user-defined literal.

• template<char... Bits>

```
cmat qpp::literals::operator"" _prj ()
```

Multi-partite qubit projector user-defined literal.


8.16.1 Detailed Description

Generic quantum computing functions.

8.17 input output.h File Reference

Input/output functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 internal::IOManipEigen qpp::disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
 Eigen expression ostream manipulator.

internal::IOManipEigen qpp::disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

• template<typename InputIterator >

internal::IOManipRange< InputIterator > qpp::disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")

Range ostream manipulator.

• template<typename Container >

internal::IOManipRange< typename Container::const_iterator > qpp::disp (const Container &c, const std ::string &separator, const std::string &start="[", const std::string &end="]", typename std::enable_if< is_← iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

• template<typename PointerType >

internal::IOManipPointer< PointerType > qpp::disp (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")

C-style pointer ostream manipulator.

• template<typename Derived >

void qpp::save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.


8.17.1 Detailed Description

Input/output functions.

8.18 instruments.h File Reference

Measurement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)
 Generalized inner product.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

ullet template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >
 std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase
 Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template < typename Derived >

 $std::tuple < idx, std::vector < double >, std::vector < cmat > > qpp::measure (const Eigen::MatrixBase < Derived > &A, const std::initializer_list < cmat > &Ks, const std::vector < idx > &target, const std::vector < idx > &dims)$

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > qpp::measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > qpp::measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, idx d=2)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.


8.18.1 Detailed Description

Measurement functions.

8.19 internal/classes/iomanip.h File Reference

Input/output manipulators.

This graph shows which files directly or indirectly include this file:



Classes

- class qpp::internal::IOManipRange< InputIterator >
- class qpp::internal::IOManipPointer< PointerType >
- class qpp::internal::IOManipEigen

Namespaces

- qpp
 - Quantum++ main namespace.
- qpp::internal

Internal utility functions, do not use them directly or modify them.


8.19.1 Detailed Description

Input/output manipulators.

8.20 internal/classes/singleton.h File Reference

Singleton pattern via CRTP.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::internal::Singleton< T >

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Namespaces

• qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


8.20.1 Detailed Description

Singleton pattern via CRTP.

8.21 internal/util.h File Reference

Internal utility functions.

This graph shows which files directly or indirectly include this file:



Classes

struct qpp::internal::Display_Impl_

Namespaces

qpp

Quantum++ main namespace.

· qpp::internal

Internal utility functions, do not use them directly or modify them.

Functions

- void qpp::internal::n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx qpp::internal::multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- $\bullet \ \ {\it template}{<} {\it typename Derived} >$

bool qpp::internal::check square mat (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

bool qpp::internal::check_vector (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_rvector (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_cvector (const Eigen::MatrixBase< Derived > &A)

• template<typename T >

bool qpp::internal::check nonzero size (const T &x) noexcept

• template<typename T1 , typename T2 >

bool qpp::internal::check_matching_sizes (const T1 &lhs, const T2 &rhs) noexcept

- bool qpp::internal::check dims (const std::vector < idx > &dims)
- template<typename Derived >

bool qpp::internal::check_dims_match_mat (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_dims_match_cvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_dims_match_rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- bool qpp::internal::check eq dims (const std::vector < idx > &dims, idx dim) noexcept
- bool app::internal::check no duplicates (std::vector< idx > v)
- bool qpp::internal::check_subsys_match_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)
- $\bullet \ \ \text{template}{<} \text{typename Derived} >$

bool qpp::internal::check_qubit_matrix (const Eigen::MatrixBase< Derived > &A) noexcept

• template<typename Derived >

bool qpp::internal::check_qubit_cvector (const Eigen::MatrixBase< Derived > &A) noexcept

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

 $bool\ qpp::internal::check_qubit_rvector\ (const\ Eigen::MatrixBase < Derived > \&A)\ noexcept$

• template<typename Derived >

bool qpp::internal::check_qubit_vector (const Eigen::MatrixBase< Derived > &A) noexcept

- bool qpp::internal::check_perm (const std::vector< idx > &perm)
- template<typename Derived1 , typename Derived2 >

 $dyn_mat < typename Derived1::Scalar > qpp::internal::kron2 (const Eigen::MatrixBase < Derived1 > &A, const Eigen::MatrixBase < Derived2 > &B)$

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::internal::dirsum2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::MatrixBase< Derived2 > &B)

• template<typename T >

void qpp::internal::variadic_vector_emplace (std::vector< T > &)

- template<typename T , typename First , typename... Args>
 - void qpp::internal::variadic_vector_emplace (std::vector< T > &v, First &&first, Args &&... args)
- idx qpp::internal::get_num_subsys (idx D, idx d)
- idx qpp::internal::get_dim_subsys (idx sz, idx N)

8.21.1 Detailed Description

Internal utility functions.

8.22 MATLAB/matlab.h File Reference

Input/output interfacing with MATLAB.

```
#include "mat.h"
#include "mex.h"
```

Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< cplx > ::type
 qpp::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::

Scalar > >::type qpp::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >
 std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.


8.22.1 Detailed Description

Input/output interfacing with MATLAB.

8.23 number_theory.h File Reference

Number theory functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

std::vector< int > qpp::x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double qpp::contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

• bigint qpp::gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint qpp::gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint qpp::lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint qpp::lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > qpp::invperm (const std::vector< idx > &perm)

Inverse permutation.

 $\bullet \ \, \text{std::vector} < \mathsf{idx} > \mathsf{qpp::compperm} \ (\mathsf{const} \ \mathsf{std::vector} < \mathsf{idx} > \& \mathsf{perm}, \ \mathsf{const} \ \mathsf{std::vector} < \mathsf{idx} > \& \mathsf{sigma}) \\$

Compose permutations.

std::vector< bigint > qpp::factors (bigint a)

Prime factor decomposition.

• bigint qpp::modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

• bigint qpp::modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple< bigint, bigint, bigint > qpp::egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint qpp::modinv (bigint a, bigint p)

Modular inverse of a mod p.

• bool qpp::isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

• bigint qpp::randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

- std::vector< std::pair< int, int > > qpp::convergents (const std::vector< int > &cf)
 Convergents.
- std::vector< std::pair< int, int > > qpp::convergents (double x, idx N)
 Convergents.


8.23.1 Detailed Description

Number theory functions.

8.24 operations.h File Reference

Quantum operation functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 const std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 idx d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

• template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std \leftrightarrow ::vector< idx > &target, const std::vector< idx > &dims)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std
::vector< idx > &target, idx d=2)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat qpp::kraus2super (const std::vector< cmat > &Ks)

Superoperator matrix.

cmat qpp::kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector< cmat > qpp::choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat qpp::choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat qpp::super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

dyn_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

template<typename Derived >

 $\label{lem:dyn_mat} $$ dyn_mat< typename\ Derived::Scalar > qpp::ptrace2\ (const\ Eigen::MatrixBase<\ Derived > \&A,\ const\ std $$::vector< idx > \&dims)$$

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Partial transpose.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2)

Partial transpose.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &perm, const std::vector< idx > &dims)

Subsystem permutation.

template<typename Derived >

 $\label{lem:dyn_mat} $$ dyn_mat< typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &perm, idx d=2)$

Subsystem permutation.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::applyQFT (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::applyTFQ (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > qpp::TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

• template<typename Derived >

 $dyn_col_vect< typename Derived::Scalar > qpp::QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)$

Qudit quantum Fourier transform.

8.24.1 Detailed Description

Quantum operation functions.

8.25 qpp.h File Reference

Quantum++ main header file, includes all other necessary headers.

```
#include <algorithm>
#include <cassert>
#include <chrono>
#include <cmath>
#include <complex>
#include <cstdlib>
#include <cstring>
#include <exception>
#include <fstream>
```

```
#include <functional>
#include <initializer_list>
#include <iomanip>
#include <iterator>
#include <limits>
#include <memory>
#include <numeric>
#include <ostream>
#include <random>
#include <sstream>
#include <stdexcept>
#include <string>
#include <tuple>
#include <type_traits>
#include <utility>
#include <vector>
#include <Eigen/Dense>
#include <Eigen/SVD>
#include "types.h"
#include "classes/exception.h"
#include "constants.h"
#include "traits.h"
#include "classes/idisplay.h"
#include "internal/util.h"
#include "internal/classes/iomanip.h"
#include "input_output.h"
#include "internal/classes/singleton.h"
#include "classes/random_devices.h"
#include "random.h"
#include "number_theory.h"
#include "functions.h"
#include "classes/init.h"
#include "classes/codes.h"
#include "classes/gates.h"
#include "classes/states.h"
#include "statistics.h"
#include "operations.h"
#include "entropies.h"
#include "entanglement.h"
#include "classes/timer.h"
#include "instruments.h"
#include "classes/reversible.h"
#include "classes/noise.h"
#include "classes/circuits.h"
```

Namespaces

dbb

Quantum++ main namespace.

Macros

#define QPP_UNUSED_

8.25.1 Detailed Description

Quantum++ main header file, includes all other necessary headers.

8.25.2 Macro Definition Documentation


8.25.2.1 QPP_UNUSED_

#define QPP_UNUSED_

8.26 random.h File Reference

Randomness-related functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

double qpp::rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

bigint qpp::rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx qpp::randidx (idx a=std::numeric_limits < idx >::min(), idx b=std::numeric_limits < idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

template<typename Derived >

Derived qpp::rand (idx rows, idx cols, double a=0, double b=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

template<>

dmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

template<>

cmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived qpp::randn (idx rows, idx cols, double mean=0, double sigma=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

• template<>

dmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

template<>

cmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

• double qpp::randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

cmat qpp::randU (idx D=2)

Generates a random unitary matrix.

cmat qpp::randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > qpp::randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat qpp::randH (idx D=2)

Generates a random Hermitian matrix.

ket qpp::randket (idx D=2)

Generates a random normalized ket (pure state vector)

cmat qpp::randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > qpp::randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > qpp::randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.


8.26.1 Detailed Description

Randomness-related functions.

8.27 statistics.h File Reference

Statistics functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

std::vector< double > qpp::uniform (idx N)

Uniform probability distribution vector.

std::vector< double > qpp::marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > qpp::marginalY (const dmat &probXY)

Marginal distribution.

• template<typename Container >

double qpp::avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_← iterable< Container >::value >::type *=nullptr)

Average.

• template<typename Container >

double qpp::cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Covariance.

• template<typename Container >

 $\label{lem:const} \mbox{double qpp::var (const std::vector< double > \&prob, const Container \&X, typename std::enable_if< is_ & iterable< Container >::value >::type *=nullptr) \\$

Variance.

• template<typename Container >

double qpp::sigma (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_← iterable< Container >::value >::type *=nullptr)

Standard deviation.

• template<typename Container >

 $\label{local-container} \begin{tabular}{ll} double & qpp::cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if < is_iterable < Container >::value >::type *=nullptr) \end{tabular}$

Correlation.

8.28 traits.h File Reference 387


8.27.1 Detailed Description

Statistics functions.

8.28 traits.h File Reference

Type traits.

This graph shows which files directly or indirectly include this file:



Classes

struct qpp::make_void< Ts >

Helper for qpp::to_void<> alias template.

struct qpp::is_iterable < T, typename >

Checks whether T is compatible with an STL-like iterable container.

- struct qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(*(std::declval < T >().end(
- struct qpp::is_matrix_expression< Derived >

Checks whether the type is an Eigen matrix expression.

struct qpp::is_complex< T >

Checks whether the type is a complex type.

struct qpp::is_complex< std::complex< T >>

Checks whether the type is a complex number type, specialization for complex types.

Namespaces

• qpp

Quantum++ main namespace.

Typedefs

```
    template<typename... Ts>
        using qpp::to_void = typename make_void< Ts... >::type
        Alias template that implements the proposal for void_t.
```


8.28.1 Detailed Description

Type traits.

8.29 types.h File Reference

Type aliases.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Typedefs

```
• using qpp::idx = std::size t
```

Non-negative integer index, make sure you use an unsigned type.

- using qpp::bigint = long long int
 - Big integer.
- using qpp::cplx = std::complex < double >

Complex number in double precision.

using qpp::ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector.

• using qpp::bra = Eigen::RowVectorXcd

Complex (double precision) dynamic Eigen row vector.

• using qpp::cmat = Eigen::MatrixXcd

Complex (double precision) dynamic Eigen matrix.

• using qpp::dmat = Eigen::MatrixXd

Real (double precision) dynamic Eigen matrix.

• template<typename Scalar >

Dynamic Eigen matrix over the field specified by Scalar.

• template<typename Scalar >

```
using qpp::dyn_col_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 >
```

Dynamic Eigen column vector over the field specified by Scalar.

 $\bullet \ \ \text{template}{<} \text{typename Scalar} >$

```
using qpp::dyn_row_vect = Eigen::Matrix< Scalar, 1, Eigen::Dynamic >
```

Dynamic Eigen row vector over the field specified by Scalar.

Type aliases.

8.30 /Users/vlad/qpp/README.md File Reference

Index

/Users/vlad/qpp/README.md, 389	avg
\sim Codes	qpp, 36
qpp::Codes, 136	
\sim Dynamic_bitset	b00
qpp::Dynamic_bitset, 158	qpp::States, 329
~Gates	b01
qpp::Gates, 174	qpp::States, 330
~IDisplay	b10
qpp::IDisplay, 190	qpp::States, 330
~IJSON	b11
	qpp::States, 330
qpp::IJSON, 192	
~Init	begin
qpp::Init, 195	qpp::QCircuitDescription, 283
~NoiseBase	bigint
qpp::NoiseBase, 242	qpp, <mark>26</mark>
\sim QCircuit	Bit_circuit
qpp::QCircuit, 269	qpp::Bit_circuit, 131
~QCircuitDescription	bloch2rho
qpp::QCircuitDescription, 283	qpp, 36
~RandomDevices	bra
qpp::RandomDevices, 317	qpp, 26
	4ρρ , 20
~Singleton	c_reg_
qpp::internal::Singleton, 321	_ -
~States	qpp::QCircuitDescription::MeasureStep, 236
qpp::States, 327	cCTRL_custom
\sim Timer	qpp::QCircuitDescription, 286
qpp::Timer, 338	cCTRL
	qpp::QCircuitDescription, 284, 285
A_	CNOTba
qpp::internal::IOManipEigen, 199	qpp::Gates, 183
absm	CNOT
qpp, 28	qpp::Bit_circuit, 131
abssq	qpp::Bit_circuit::Gate_count, 170
qpp, 29	qpp::Gates, 183
	CTRL custom
adjoint	-
qpp, 30	qpp::QCircuitDescription, 288
all	CTRL
qpp::Dynamic_bitset, 158	qpp::Gates, 175
anticomm	qpp::QCircuitDescription, 286–288
qpp, 30	cbegin
any	qpp::QCircuitDescription, 283
qpp::Dynamic_bitset, 158	cend
apply	qpp::QCircuitDescription, 286
qpp, 31–33	check_cvector
applyCTRL	qpp::internal, 120
qpp, 33, 34	check_dims
applyQFT	qpp::internal, 120
qpp, 35	check_dims_match_cvect
applyTFQ	qpp::internal, 120
app. 35	check dims match mat

qpp::internal, 121	compperm
check_dims_match_rvect	qpp, 38
qpp::internal, 121	compute_probs_
check_eq_dims	qpp::NoiseBase, 242
qpp::internal, 121	compute_state_
check_matching_sizes	qpp::NoiseBase, 242
qpp::internal, 121	concurrence
check_no_duplicates	qpp, 40
qpp::internal, 121	conjugate
check_nonzero_size	qpp, 40
qpp::internal, 121	const_iterator
check_perm	qpp::QCircuitDescription, 281
qpp::internal, 122	constants.h, 363
check_qubit_cvector	contfrac2x
qpp::internal, 122	qpp, 40
check_qubit_matrix	convergents
qpp::internal, 122	qpp, 41
check_qubit_rvector	cor
app::internal, 122	qpp, 42
check_qubit_vector	cosm
qpp::internal, 122	qpp, 42
check_rvector	count
qpp::internal, 122	qpp::Dynamic_bitset, 158
check_square_mat	COV
app::internal, 123	qpp, 43
check_subsys_match_dims	cplx
qpp::internal, 123	qpp, 27
check_vector	-
qpp::internal, 123 choi2kraus	qpp::QCircuitDescription::GateStep, 187 CustomException
	qpp::exception::CustomException, 138
qpp, 36 choi2super	cwise
·	qpp, 43
qpp, 37 chop	CZ
qpp, 116	qpp::Gates, 183
chop_	appaatoo, roo
qpp::internal::IOManipEigen, 199	d_
classes/circuits.h, 353	qpp::NoiseBase, 245
classes/codes.h, 354	qpp::QCircuitDescription, 300
classes/exception.h, 355	data
classes/gates.h, 357	qpp::Dynamic_bitset, 158
classes/idisplay.h, 358	det
classes/init.h, 358	qpp, 44
classes/noise.h, 359	difference_type
classes/random_devices.h, 360	qpp::QCircuitDescription::iterator, 213
classes/reversible.h, 361	dirsum
classes/states.h, 361	qpp, 44–46
classes/timer.h, 362	dirsum2
cmat	qpp::internal, 123
qpp, 26	dirsumpow
Codes	qpp, 46
qpp::Codes, 136	disp
codeword	qpp, 47, 48
qpp::Codes, 136	display
comm	qpp::Dynamic_bitset, 159
qpp, 37	qpp::IDisplay, 190
complement	qpp::QCircuit, 269
qpp, 38	qpp::QCircuitDescription, 289

qpp::QCircuitDescription::iterator::value_type_←	qpp::exception::MatrixNotCvector, 221
, 349	qpp::exception::MatrixNotRvector, 223
qpp::Timer, 338	qpp::exception::MatrixNotSquare, 225
qpp::internal::IOManipEigen, 199	qpp::exception::MatrixNotSquareNorCvector, 227
qpp::internal::IOManipPointer, 201	qpp::exception::MatrixNotSquareNorRvector, 229
qpp::internal::IOManipRange, 205	qpp::exception::MatrixNotSquareNorVector, 231
display_impl_	qpp::exception::MatrixNotVector, 233
qpp::internal::Display_Impl_, 152	qpp::exception::NoCodeword, 238
dits_	qpp::exception::NotBipartite, 248
qpp::QCircuit, 275	qpp::exception::NotImplemented, 250
dmat	qpp::exception::NotQubitCvector, 252
qpp, 27	qpp::exception::NotQubitMatrix, 254
dyn_col_vect	qpp::exception::NotQubitRvector, 256
qpp, 27	qpp::exception::NotQubitSubsys, 258
dyn mat	qpp::exception::NotQubitVector, 260
qpp, 27	qpp::exception::OutOfRange, 262
dyn_row_vect	qpp::exception::PermInvalid, 264
qpp, 27	qpp::exception::PermMismatchDims, 266
Dynamic_bitset	qpp::exception::QuditAlreadyMeasured, 312
qpp::Bit_circuit, 132	qpp::exception::SizeMismatch, 323
qpp::Dynamic_bitset, 157	qpp::exception::SubsysMismatchDims, 335
	qpp::exception::TypeMismatch, 342
ee	qpp::exception::UndefinedType, 344
qpp, 116	qpp::exception::Unknown, 346
egcd	qpp::exception::ZeroSize, 352
qpp, 49	execute
eig	qpp::QCircuit, 270
qpp, 49	expandout
elem	•
qpp::QCircuitDescription::iterator, 217	qpp::Gates, 175, 176
end	experimental/experimental.h, 367
qpp::QCircuitDescription, 289	expm
	qpp, 52
end_	5050
qpp::Timer, 340	FRED
qpp::internal::IOManipPointer, 202	qpp::Bit_circuit, 132
qpp::internal::IOManipRange, 205	qpp::Bit_circuit::Gate_count, 171
entanglement	qpp::Gates, 183
qpp, 50	factors
entanglement.h, 364	qpp, 53
entropies.h, 366	Fd
entropy	qpp::Gates, 177
qpp, 51	fill_Ks_
eps	app::QuditDepolarizingNoise, 315
qpp, 116	fill_probs_
evals	
	qpp::QuditDepolarizingNoise, 315
qpp, 51	first_
evects	qpp::internal::IOManipRange, 206
qpp, 52	flip
Exception	qpp::Dynamic_bitset, 159
qpp::exception::DimsInvalid, 141	functions.h, 367
qpp::exception::DimsMismatchCvector, 143	funm
qpp::exception::DimsMismatchMatrix, 145	qpp, 53
qpp::exception::DimsMismatchRvector, 147	
qpp::exception::DimsMismatchVector, 149	GHZ
qpp::exception::DimsNotEqual, 151	qpp::States, 330
qpp::exception::Duplicates, 154	gate
qpp::exception::Exception, 169	qpp::QCircuitDescription, 290, 291
qpp::exception::Exception, 199 qpp::exception::InvalidIterator, 197	* *
	gate_
qpp::exception::MatrixMismatchSubsys, 219	qpp::QCircuitDescription::GateStep, 187

gate_count	qpp::QCircuitDescription, 294
qpp::Bit_circuit, 134	get_measurements
gate custom	qpp::QCircuitDescription, 294
qpp::QCircuitDescription, 291	get_name
gate_fan	qpp::Gates, 178
qpp::QCircuitDescription, 291, 292	qpp::QCircuitDescription, 294
	get nc
gate_type_	qpp::QCircuitDescription, 295
qpp::QCircuitDescription::GateStep, 187	
GateStep	get_non_measured
qpp::QCircuitDescription::GateStep, 186	qpp::QCircuitDescription, 295
GateType	get_not_measured
qpp::QCircuitDescription, 281	qpp::QCircuit, 272
Gates	get_nq
qpp::Gates, 174	qpp::QCircuitDescription, 295
gates	get_num_subsys
qpp::QCircuitDescription, 300	qpp::internal, 123
gates_ip_	get_prng
qpp::QCircuitDescription::iterator::value_type_ ←	qpp::RandomDevices, 318
	get_probs
, 349	qpp::NoiseBase, 244
gcd	qpp::QCircuit, 272
qpp, 54	
gconcurrence	get_psi
qpp, 54	qpp::QCircuit, 272
generated_	get_ref_psi
qpp::NoiseBase, 245	qpp::QCircuit, 273
get	get_relative_pos_
qpp::Dynamic_bitset, 160	qpp::QCircuit, 273
get_Ks	get_step_count
qpp::NoiseBase, 243	qpp::QCircuitDescription, 295
get_circuit_description	get_thread_local_instance
	qpp::internal::Singleton, 321
qpp::QCircuit, 270	grams
get_d	qpp, 55, 56
qpp::NoiseBase, 243	-11-1-7 7
qpp::QCircuitDescription, 293	Н
get_dim_subsys	qpp::Gates, 183
qpp::internal, 123	heig
get_dit	_
qpp::QCircuit, 271	qpp, 56
get_dits	hevals
qpp::QCircuit, 271	qpp, 57
get_duration	hevects
qpp::Timer, 339	qpp, 5 7
get_gate_count	<u>i_</u>
qpp::QCircuitDescription, 293	qpp::NoiseBase, 245
get_gates	IDisplay
qpp::QCircuitDescription, 293	qpp::IDisplay, 189
get_instance	IJSON
qpp::internal::Singleton, 321	qpp::IJSON, 192
get_last_idx	IOManipEigen
qpp::NoiseBase, 243	qpp::internal::IOManipEigen, 199
get_last_K	IOManipPointer
qpp::NoiseBase, 244	qpp::internal::IOManipPointer, 201
get_last_p	IOManipRange
qpp::NoiseBase, 244	qpp::internal::IOManipRange, 204, 205
get_measured	ld
qpp::QCircuit, 271, 272	qpp::Gates, 178
qpp::QCircuitDescription, 293, 294	ld2
get_measurement_count	qpp::Gates, 184

idx	last_
qpp, 28	qpp::internal::IOManipRange, 206
idx_infty	lcm
qpp, 116	qpp, 63
index_	load
qpp::Dynamic_bitset, 160	qpp, 64
infty	qpp::RandomDevices, 318
qpp, 116	loadMATLAB
Init	qpp, 64, 65
qpp::Init, 195	logdet
input_output.h, 372	qpp, 66
instruments.h, 373	logm
internal/classes/iomanip.h, 374	qpp, 66
internal/classes/singleton.h, 375	lognegativity
internal/util.h, 376	qpp, 67
internal::Singleton < const Codes >	MATI AD/motion h 279
qpp::Codes, 137	MATLAB/matlab.h, 378
internal::Singleton < const Gates >	MODMUL
qpp::Gates, 183	qpp::Gates, 178
internal::Singleton < const Init >	marginalX
qpp::Init, 195	qpp, 67
internal::Singleton < const States >	marginalY
qpp::States, 329	qpp, 69
internal::Singleton < RandomDevices >	mats_
qpp::RandomDevices, 319	qpp::QCircuitDescription::MeasureStep, 236
inverse	maxn
qpp, 57	qpp, 116
invperm	measure
qpp, 58	qpp, 69–74
ip	measure_seq
qpp, 58, 59	qpp, 74, 75
ip_	MeasureStep
dpp::QCircuitDescription::iterator::value_type_←	qpp::QCircuitDescription::MeasureStep, 235
, 349	MeasureType
isprime	qpp::QCircuitDescription, 282
qpp, 59	measured_ qpp::QCircuitDescription, 300
iterator	
qpp::QCircuitDescription::iterator, 214	measurement_type_ qpp::QCircuitDescription::MeasureStep, 236
iterator_category	
qpp::QCircuitDescription::iterator, 213	measurements_ qpp::QCircuitDescription, 300
	measurements ip
jn	qpp::QCircuitDescription::iterator::value_type_←
qpp::States, 327	, 350
-11-11	measureV
ket	qpp::QCircuitDescription, 296
qpp, 28	measureZ
kraus2choi	qpp::QCircuitDescription, 297
qpp, 59	mes
kraus2super	qpp::States, 327
qpp, 60	minus
kron	qpp::States, 328
qpp, 60–62	
qpp, 00–02 kron2	mket qpp, 75, 76
qpp::internal, 124	modiny
kronpow	
•	qpp, 76 modmul
qpp, 62	
Ks_ qpp::NoiseBase, 246	qpp, 77
4pp1000000000000000000000000000000000	modpow

qpp, 77	operator-
mprj	qpp::Dynamic_bitset, 161
qpp, 78	operator= qpp::IDisplay, 190
msg_ qpp::exception::Exception, 170	qpp::IJSON, 192, 193
multiidx2n	qpp::QCircuitDescription::iterator, 215
qpp, 79	qpp::QCircuitDescription::iterator::value_type_←
qpp::internal, 124	, 349
entrice and an area	qpp::Timer, 339
n2multiidx	qpp::internal::IOManipPointer, 202
qpp, 79	qpp::internal::IOManipRange, 205
qpp::internal, 124	qpp::internal::Singleton, 321
N_	operator==
qpp::Dynamic_bitset, 165	qpp::Dynamic_bitset, 162
qpp::internal::IOManipPointer, 202	qpp::QCircuitDescription::iterator, 216
NOT	operator""_bra
qpp::Bit_circuit, 132	qpp::literals, 125
qpp::Bit_circuit::Gate_count, 171	operator"" _i
name_	qpp, 82
<pre>qpp::QCircuitDescription, 300 qpp::QCircuitDescription::GateStep, 187</pre>	qpp::literals, 125
qpp::QCircuitDescription::MeasureStep, 236	operator"" _ket
nc_	qpp::literals, 126 operator"" _prj
qpp::QCircuitDescription, 301	qpp::literals, 126
negativity	qppiiterais, 120
qpp, 80	p_
noise_type	qpp::internal::IOManipPointer, 202
qpp::NoiseBase, 241	pGHZ
NoiseBase	qpp::States, 331
qpp::NoiseBase, 241	pb00
none	qpp::States, 330
qpp::Dynamic_bitset, 160	pb01
norm	qpp::States, 330
qpp, 81	pb10
normalize	qpp::States, 331
qpp, 81	pb11
nq_	qpp::States, 331
qpp::QCircuitDescription, 301	pi
number_theory.h, 378	qpp, 117 plus
offset_	qpp::States, 328
qpp::Dynamic_bitset, 161	pointer
omega	qpp::QCircuitDescription::iterator, 213
qpp, 82	powm
one	qpp, 82
qpp::States, 328	prj
operations.h, 380	qpp, 83
operator!=	prng_
qpp::Dynamic_bitset, 161	qpp::RandomDevices, 319
qpp::QCircuitDescription::iterator, 214	probs_
operator<<	qpp::NoiseBase, 246
qpp::IDisplay, 191	qpp::QCircuit, 276
qpp::QCircuitDescription, 298, 299	prod
operator*	qpp, 83, 84
qpp::QCircuitDescription::iterator, 215	psi_
operator()	qpp::QCircuit, 276
qpp::NoiseBase, 244, 245	ptrace
operator++	qpp, 84, 85
qpp::QCircuitDescription::iterator, 215	ptrace1

qpp, 85, 86	cosm, 42
ptrace2	cov, 43
qpp, 86, 87	cplx, 27
ptranspose	cwise, 43
qpp, 87, 88	det, 44
pW	dirsum, 44-46
qpp::States, 331	dirsumpow, 46
px0	disp, 47, 48
qpp::States, 331	dmat, 27
px1	dyn_col_vect, 27
qpp::States, 331	dyn_mat, 27
py0	dyn_row_vect, 27
qpp::States, 332	ee, 116
py1 qpp::States, 332	egcd, 49
pz0	eig, 49
qpp::States, 332	entanglement, 50
pz1	entropy, 51
qpp::States, 332	eps, 116
4ppotatoo, 002	evals, 51
QCircuit	evects, 52
qpp::QCircuit, 269	expm, 52
QCircuitDescription	factors, 53
qpp::QCircuitDescription, 282	funm, 53
QFT	gcd, 54
qpp, 88	gconcurrence, 54 grams, 55, 56
qpp::QCircuitDescription, 297	
QPP_UNUSED_	heig, 56 hevals, 57
qpp.h, 384	hevects, 57
qcd_	idx, 28
qpp::QCircuit, 276	idx_infty, 116
qpp::QCircuitDescription::iterator, 217	infty, 116
qmutualinfo	inverse, 57
qpp, 89	inverse, 57
qpp, 13	ip, 58, 59
absm, 28	isprime, 59
abssq, 29	ket, 28
adjoint, 30	kraus2choi, 59
anticomm, 30	kraus2super, 60
apply, 31–33	kron, 60–62
applyCTRL, 33, 34	141011, 00 02
• • •	kronpow 62
applyQFT, 35	kronpow, 62
applyQFT, 35 applyTFQ, 35	lcm, 63
applyQFT, 35 applyTFQ, 35 avg, 36	lcm, 63 load, 64
applyQFT, 35 applyTFQ, 35 avg, 36 bigint, 26	lcm, 63 load, 64 loadMATLAB, 64, 65
applyQFT, 35 applyTFQ, 35 avg, 36 bigint, 26 bloch2rho, 36	lcm, 63 load, 64 loadMATLAB, 64, 65 logdet, 66
applyQFT, 35 applyTFQ, 35 avg, 36 bigint, 26 bloch2rho, 36 bra, 26	lcm, 63 load, 64 loadMATLAB, 64, 65 logdet, 66 logm, 66
applyQFT, 35 applyTFQ, 35 avg, 36 bigint, 26 bloch2rho, 36 bra, 26 choi2kraus, 36	lcm, 63 load, 64 loadMATLAB, 64, 65 logdet, 66 logm, 66 lognegativity, 67
applyQFT, 35 applyTFQ, 35 avg, 36 bigint, 26 bloch2rho, 36 bra, 26 choi2kraus, 36 choi2super, 37	lcm, 63 load, 64 loadMATLAB, 64, 65 logdet, 66 logm, 66
applyQFT, 35 applyTFQ, 35 avg, 36 bigint, 26 bloch2rho, 36 bra, 26 choi2kraus, 36 choi2super, 37 chop, 116	lcm, 63 load, 64 loadMATLAB, 64, 65 logdet, 66 logm, 66 lognegativity, 67 marginalX, 67
applyQFT, 35 applyTFQ, 35 avg, 36 bigint, 26 bloch2rho, 36 bra, 26 choi2kraus, 36 choi2super, 37 chop, 116 cmat, 26	lcm, 63 load, 64 loadMATLAB, 64, 65 logdet, 66 logm, 66 lognegativity, 67 marginalX, 67 marginalY, 69
applyQFT, 35 applyTFQ, 35 avg, 36 bigint, 26 bloch2rho, 36 bra, 26 choi2kraus, 36 choi2super, 37 chop, 116 cmat, 26 comm, 37	lcm, 63 load, 64 loadMATLAB, 64, 65 logdet, 66 logm, 66 lognegativity, 67 marginalX, 67 marginalY, 69 maxn, 116
applyQFT, 35 applyTFQ, 35 avg, 36 bigint, 26 bloch2rho, 36 bra, 26 choi2kraus, 36 choi2super, 37 chop, 116 cmat, 26	lcm, 63 load, 64 loadMATLAB, 64, 65 logdet, 66 logm, 66 lognegativity, 67 marginalX, 67 marginalY, 69 maxn, 116 measure, 69–74
applyQFT, 35 applyTFQ, 35 avg, 36 bigint, 26 bloch2rho, 36 bra, 26 choi2kraus, 36 choi2super, 37 chop, 116 cmat, 26 comm, 37 complement, 38	lcm, 63 load, 64 loadMATLAB, 64, 65 logdet, 66 logm, 66 lognegativity, 67 marginalX, 67 marginalY, 69 maxn, 116 measure, 69–74 measure_seq, 74, 75
applyQFT, 35 applyTFQ, 35 avg, 36 bigint, 26 bloch2rho, 36 bra, 26 choi2kraus, 36 choi2super, 37 chop, 116 cmat, 26 comm, 37 complement, 38 compperm, 38	lcm, 63 load, 64 loadMATLAB, 64, 65 logdet, 66 logm, 66 lognegativity, 67 marginalX, 67 marginalY, 69 maxn, 116 measure, 69–74 measure_seq, 74, 75 mket, 75, 76
applyQFT, 35 applyTFQ, 35 avg, 36 bigint, 26 bloch2rho, 36 bra, 26 choi2kraus, 36 choi2super, 37 chop, 116 cmat, 26 comm, 37 complement, 38 compperm, 38 concurrence, 40	lcm, 63 load, 64 loadMATLAB, 64, 65 logdet, 66 logm, 66 lognegativity, 67 marginalX, 67 marginalY, 69 maxn, 116 measure, 69–74 measure_seq, 74, 75 mket, 75, 76 modinv, 76
applyQFT, 35 applyTFQ, 35 avg, 36 bigint, 26 bloch2rho, 36 bra, 26 choi2kraus, 36 choi2super, 37 chop, 116 cmat, 26 comm, 37 complement, 38 compperm, 38 concurrence, 40 conjugate, 40	lcm, 63 load, 64 loadMATLAB, 64, 65 logdet, 66 logm, 66 lognegativity, 67 marginalX, 67 marginalY, 69 maxn, 116 measure, 69–74 measure_seq, 74, 75 mket, 75, 76 modinv, 76 modmul, 77
applyQFT, 35 applyTFQ, 35 avg, 36 bigint, 26 bloch2rho, 36 bra, 26 choi2kraus, 36 choi2super, 37 chop, 116 cmat, 26 comm, 37 complement, 38 compperm, 38 concurrence, 40 conjugate, 40 contfrac2x, 40	lcm, 63 load, 64 loadMATLAB, 64, 65 logdet, 66 logm, 66 lognegativity, 67 marginalX, 67 marginalY, 69 maxn, 116 measure, 69–74 measure_seq, 74, 75 mket, 75, 76 modinv, 76 modmul, 77 modpow, 77

n2multiidx, 79	qpp.h, 382
negativity, 80	QPP_UNUSED_, 384
norm, 81	qpp::Bit_circuit, 129
normalize, 81	Bit_circuit, 131
omega, 82	CNOT, 131
operator"" _i, 82	Dynamic_bitset, 132
pi, 117	FRED, 132
powm, 82	gate_count, 134
prj, 83	NOT, 132
prod, 83, 84	reset, 132
ptrace, 84, 85	SWAP, 133
ptrace1, 85, 86	TOF, 133
ptrace2, 86, 87	X, 133
ptranspose, 87, 88	qpp::Bit_circuit::Gate_count, 170
QFT, 88	CNOT, 170
qmutualinfo, 89	FRED, 171
rand, 90–92	NOT, 171
randH, 92	SWAP, 171
randidx, 93	TOF, 171
randket, 93	X, 171
randkraus, 93	qpp::Codes, 134
randn, 94, 95	~Codes, 136
randperm, 96	Codes, 136
randprime, 96	codeword, 136
randprob, 97	internal::Singleton< const Codes >, 137
randrho, 97	Type, 135
randU, 97	qpp::Dynamic_bitset, 155
randV, 98	~Dynamic_bitset, 158
renyi, 98, 99	all, 158
reshape, 99	any, 158
rho2bloch, 100	count, 158
rho2pure, 100	data, 158
save, 101	display, 159
saveMATLAB, 101, 102	Dynamic_bitset, 157
schatten, 102	flip, 159
schmidtA, 103	get, 160
schmidtB, 103, 104	index_, 160
schmidtcoeffs, 104, 105	N_, 165
schmidtprobs, 105, 106	none, 160
sigma, 106	offset_, 161
sinm, 107 spectralpowm, 107	operator!=, 161
•	operator-, 161 operator==, 162
sqrtm, 108	rand, 162, 163
sum, 108, 109	
super2choi, 109	reset, 163
svals, 110	set, 163, 164
svd, 110 svdU, 110	size, 164
svdV, 111	storage_size, 164
	storage_size_, 165
syspermute, 111, 112 TFQ, 112	storage_type, 157 to_string, 164
	_ -
to_void, 28 trace, 112	v_, 165 value_type, 157
transpose, 113	qpp::Gates, 172
tsallis, 113, 114	\sim Gates, 174
uniform, 114	CNOTba, 183
var, 115	CNOT, 183
x2contfrac, 115	CTRL, 175
A200111140, 110	J. 112, 170

C7 100	consultaine Page / T > 200
CZ, 183	qpp::NoiseBase< T >, 239
expandout, 175, 176	qpp::NoiseType, 246
FRED, 183	qpp::NoiseType::StateDependent, 324
Fd, 177 Gates, 174	<pre>qpp::NoiseType::StateIndependent, 324 qpp::QCircuit, 267</pre>
get name, 178	~QCircuit, 269
-	
H, 183	display, 269
ld, 178 ld2, 184	dits_, 275
internal::Singleton< const Gates >, 183	execute, 270 get circuit description, 270
MODMUL, 178	get_dit, 271
Rn, 179	get_dits, 271
RX, 179	get_measured, 271, 272
RY, 180	get_not_measured, 272
RZ, 180	get_probs, 272
S, 184	get_pioss, 272 get_psi, 272
SWAPd, 180	get_ref_psi, 273
SWAP, 184	get relative pos , 273
T, 184	probs_, 276
TOF, 184	psi_, 276
X, 184	QCircuit, 269
Xd, 182	qcd_, 276
Y, 185	reset, 273
Z, 185	set_dit, 273
Zd, 182	set_measured_, 275
qpp::IDisplay, 188	subsys_, 276
∼IDisplay, 190	to_JSON, 275
display, 190	qpp::QCircuitDescription, 277
IDisplay, 189	~QCircuitDescription, 283
operator<<, 191	begin, 283
operator=, 190	cCTRL_custom, 286
qpp::IJSON, 191	cCTRL, 284, 285
\sim IJSON, 192	CTRL_custom, 288
IJSON, 192	CTRL, 286–288
operator=, 192, 193	cbegin, 283
to_JSON, 193	cend, 286
qpp::Init, 193	const_iterator, 281
∼Init, 195	d_, 300
Init, 195	display, 289
internal::Singleton< const Init >, 195	end, 289
qpp::NoiseBase	gate, 290, 291
∼NoiseBase, 242	gate_custom, 291
compute_probs_, 242	gate_fan, 291, 292
compute_state_, 242	GateType, 281
d_, 245	gates_, 300
generated_, 245	get_d, 293
get_Ks, 243	get_gate_count, 293
get_d, 243	get_gates, 293
get_last_idx, 243	get_measurement_count_204
get_last_K, 244	get_measurement_count, 294
get_last_p, 244 get_probs, 244	get_measurements, 294 get_name, 294
i , 245	get_nc, 295
r_, 243 Ks_, 246	get_non_measured, 295
noise_type, 241	get_nq, 295
NoiseBase, 241	get_step_count, 295
operator(), 244, 245	MeasureType, 282
probs_, 246	measured_, 300
F. 222_1 4	

measurements_, 300	qpp::QubitDepolarizingNoise, 306
measureV, 296	QubitDepolarizingNoise, 307
measureZ, 297	qpp::QubitPhaseDampingNoise, 308
name_, 300	QubitPhaseDampingNoise, 309
nc_, 301	qpp::QubitPhaseFlipNoise, 309
nq_, 301	QubitPhaseFlipNoise, 310
operator<<, 298, 299	qpp::QuditDepolarizingNoise, 313
•	
QCircuitDescription, 282	fill_Ks_, 315
QFT, 297	fill_probs_, 315
step_types_, 301	QuditDepolarizingNoise, 314
StepType, 282	qpp::RandomDevices, 316
TFQ, 297	\sim RandomDevices, 317
to_JSON, 298	get_prng, 318
qpp::QCircuitDescription::GateStep, 185	internal::Singleton < RandomDevices >, 319
ctrl_, 187	load, 318
gate_, 187	prng_, 319
gate_type_, 187	RandomDevices, 317
GateStep, 186	rd_, 319
name_, 187	save, 318
target_, 187	qpp::States, 324
qpp::QCircuitDescription::MeasureStep, 234	~States, 327
c_reg_, 236	b00, 329
mats_, 236	b01, 330
MeasureStep, 235	b10, 330
measurement_type_, 236	b11, 330
name_, 236	GHZ, 330
target_, 236	internal::Singleton< const States >, 329
qpp::QCircuitDescription::iterator, 212	jn, 327
difference_type, 213	mes, 327
elem_, 217	minus, 328
iterator, 214	one, 328
iterator_category, 213	pGHZ, 331
	•
operator!=, 214	pb00, 330
operator*, 215	pb01, 330
operator++, 215	pb10, 331
operator=, 215	pb11, 331
operator==, 216	plus, 328
pointer, 213	pW, 331
qcd_, 217	px0, 331
reference, 213	px1, 331
set_begin_, 216	py0, 332
set_end_, 216	py1, 332
value_type, 214	pz0, 332
qpp::QCircuitDescription::iterator::value_type_, 347	pz1, 332
display, 349	States, 327
gates_ip_, 349	W, 332
ip_, 349	x0, 332
measurements_ip_, 350	x1, 333
operator=, 349	y0, 333
type_, 350	y1, 333
value_type_, 348	z0, 333
value_type_qcd_, 350	z1, 333
qpp::QubitAmplitudeDampingNoise, 302	zero, 329
QubitAmplitudeDampingNoise, 303	qpp::Timer
qpp::QubitBitFlipNoise, 303	∼Timer, 338
QubitBitFlipNoise, 304	display, 338
qpp::QubitBitPhaseFlipNoise, 305	end_, 340
QubitBitPhaseFlipNoise, 306	get_duration, 339

operator=, 339	Exception, 229
start_, 340	type_description, 230
tic, 339	qpp::exception::MatrixNotSquareNorVector, 230
tics, 340	Exception, 231
Timer, 337, 338	type_description, 232
toc, 340	qpp::exception::MatrixNotVector, 232
qpp::Timer< T, CLOCK_T >, 336	Exception, 233
qpp::exception, 117	type_description, 234
qpp::exception::CustomException, 137	qpp::exception::NoCodeword, 237
CustomException, 138	Exception, 238
type description, 139	type description, 239
what_, 139	qpp::exception::NotBipartite, 247
qpp::exception::DimsInvalid, 140	Exception, 248
Exception, 141	type_description, 248
type_description, 141	qpp::exception::NotImplemented, 249
qpp::exception::DimsMismatchCvector, 142	Exception, 250
Exception, 143	type_description, 250
type_description, 143	qpp::exception::NotQubitCvector, 251
qpp::exception::DimsMismatchMatrix, 144	Exception, 252
Exception, 145	type_description, 252
type description, 145	qpp::exception::NotQubitMatrix, 253
qpp::exception::DimsMismatchRvector, 146	Exception, 254
Exception, 147	type_description, 254
	qpp::exception::NotQubitRvector, 255
type_description, 147	
app::exception::DimsMismatchVector, 148	Exception, 256
Exception, 149	type_description, 256
type_description, 149	qpp::exception::NotQubitSubsys, 257
qpp::exception::DimsNotEqual, 150	Exception, 258
Exception, 151	type_description, 258
type_description, 151	qpp::exception::NotQubitVector, 259
qpp::exception::Duplicates, 153	Exception, 260
Exception, 154	type_description, 260
type_description, 154	qpp::exception::OutOfRange, 261
qpp::exception::Exception, 166	Exception, 262
Exception, 169	type_description, 262
msg_, 170	qpp::exception::PermInvalid, 263
type_description, 169	Exception, 264
what, 169	type_description, 264
where_, 170	qpp::exception::PermMismatchDims, 265
qpp::exception::InvalidIterator, 195	Exception, 266
Exception, 197	type_description, 266
type_description, 197	qpp::exception::QuditAlreadyMeasured, 311
qpp::exception::MatrixMismatchSubsys, 218	Exception, 312
Exception, 219	type_description, 313
type_description, 220	qpp::exception::SizeMismatch, 322
qpp::exception::MatrixNotCvector, 220	Exception, 323
Exception, 221	type_description, 323
type_description, 222	qpp::exception::SubsysMismatchDims, 334
qpp::exception::MatrixNotRvector, 222	Exception, 335
Exception, 223	type_description, 335
type_description, 224	qpp::exception::TypeMismatch, 341
qpp::exception::MatrixNotSquare, 224	Exception, 342
Exception, 225	type_description, 343
type_description, 226	qpp::exception::UndefinedType, 343
qpp::exception::MatrixNotSquareNorCvector, 226	Exception, 344
Exception, 227	type_description, 345
type_description, 228	qpp::exception::Unknown, 345
qpp::exception::MatrixNotSquareNorRvector, 228	Exception, 346
appoxoopiioiiiviatiixivitoquai ervoii (vectoi, 220	Exooption, 070

type_description, 347	qpp::internal::Singleton
qpp::exception::ZeroSize, 351	\sim Singleton, 321
Exception, 352	get_instance, 321
type_description, 352	get_thread_local_instance, 321
qpp::experimental, 119	operator=, 321
qpp::internal, 119	Singleton, 320, 321
check_cvector, 120	qpp::internal::Singleton< T >, 319
check_dims, 120	qpp::is_complex < std::complex < T > >, 208
check_dims_match_cvect, 120	qpp::is_complex< T >, 207
check_dims_match_mat, 121	<pre>qpp::is_iterable< T, to_void< decltype(std::declval< T</pre>
check_dims_match_rvect, 121	$>$ ().begin()), decltype(std::declval< T $>$ (). \leftarrow
check_eq_dims, 121	end()), decltype(*(std::declval< T >().←
check_matching_sizes, 121	begin()))>>, 210
check_no_duplicates, 121	qpp::is_iterable < T, typename >, 209
check_nonzero_size, 121	qpp::is_matrix_expression< Derived >, 211
check_perm, 122	qpp::literals, 125
check_qubit_cvector, 122	operator"" _bra, 125
check_qubit_cvector, 122	operator"" _i, 125
— · —	operator"" _ket, 126
check_qubit_rvector, 122	operator"" _prj, 126
check_qubit_vector, 122	gpp::make void
check_rvector, 122	type, 218
check_square_mat, 123	qpp::make_void $<$ Ts $>$, 217
check_subsys_match_dims, 123	QubitAmplitudeDampingNoise
check_vector, 123	qpp::QubitAmplitudeDampingNoise, 303
dirsum2, 123	QubitBitFlipNoise
get_dim_subsys, 123	qpp::QubitBitFlipNoise, 304
get_num_subsys, 123	QubitBitPhaseFlipNoise
kron2, 124	qpp::QubitBitPhaseFlipNoise, 306
multiidx2n, 124	
n2multiidx, 124	QubitDepolarizingNoise
variadic_vector_emplace, 124	qpp::QubitDepolarizingNoise, 307 QubitPhaseDampingNoise
qpp::internal::Display_Impl_, 152	. •
display_impl_, 152	qpp::QubitPhaseDampingNoise, 309
qpp::internal::IOManipEigen, 197	QubitPhaseFlipNoise
A_, 199	qpp::QubitPhaseFlipNoise, 310
chop_, 199	QuditDepolarizingNoise
display, 199	qpp::QuditDepolarizingNoise, 314
IOManipEigen, 199	rand
qpp::internal::IOManipPointer	qpp, 90–92
display, 201	qpp::Dynamic_bitset, 162, 163
end_, 202	randH
IOManipPointer, 201	qpp, 92
N_, 202	randidx
operator=, 202	qpp, 93
p_, 202	randket
separator_, 202	qpp, 93
start , 203	randkraus
qpp::internal::IOManipPointer< PointerType >, 200	qpp, 93
qpp::internal::IOManipRange	randn
display, 205	qpp, 94, 95
end_, 205	random.h, 384
first_, 206	RandomDevices
IOManipRange, 204, 205	qpp::RandomDevices, 317
last_, 206	randperm
operator=, 205	•
separator_, 206	qpp, 96 randprime
start_, 206	
qpp::internal::IOManipRange< InputIterator >, 203	qpp, 96 randprob
Appcomaoma.npi tange \ mputiterator 200	Tanapion

ann 07	ann::Dynamic hitset 162 164
qpp, 97	qpp::Dynamic_bitset, 163, 164
randrho	set_begin_
qpp, 97	qpp::QCircuitDescription::iterator, 216
randU	set_dit
qpp, 9 7	qpp::QCircuit, 273
randV	set_end_
qpp, 98	qpp::QCircuitDescription::iterator, 216
rd_	set_measured_
qpp::RandomDevices, 319	qpp::QCircuit, 275
reference	sigma
<pre>qpp::QCircuitDescription::iterator, 213</pre>	qpp, 106
renyi	Singleton
qpp, 98, 99	qpp::internal::Singleton, 320, 321
reset	sinm
qpp::Bit_circuit, 132	
	qpp, 107
qpp::Dynamic_bitset, 163	size
qpp::QCircuit, 273	qpp::Dynamic_bitset, 164
reshape	spectralpowm
qpp, 99	qpp, 107
rho2bloch	sqrtm
qpp, 100	qpp, 108
rho2pure	start_
qpp, 100	qpp::Timer, 340
Rn	qpp::internal::IOManipPointer, 203
qpp::Gates, 179	qpp::internal::IOManipRange, 206
RX	States
qpp::Gates, 179	qpp::States, 327
RY	
	statistics.h, 386
qpp::Gates, 180	step_types_
RZ	qpp::QCircuitDescription, 301
qpp::Gates, 180	StepType
6	qpp::QCircuitDescription, 282
S	storage_size
qpp::Gates, 184	qpp::Dynamic_bitset, 164
SWAPd	storage_size_
qpp::Gates, 180	qpp::Dynamic_bitset, 165
SWAP	storage_type
qpp::Bit_circuit, 133	gpp::Dynamic bitset, 157
qpp::Bit_circuit::Gate_count, 171	subsys_
qpp::Gates, 184	qpp::QCircuit, 276
save	sum
qpp, 101	
qpp::RandomDevices, 318	qpp, 108, 109
saveMATLAB	super2choi
	qpp, 109
qpp, 101, 102	svals
schatten	qpp, 110
qpp, 102	svd
schmidtA	qpp, 110
qpp, 103	svdU
schmidtB	qpp, 110
qpp, 103, 104	svdV
schmidtcoeffs	qpp, 111
qpp, 104, 105	syspermute
schmidtprobs	
qpp, 105, 106	qpp, 111, 112
separator_	Т
qpp::internal::IOManipPointer, 202	qpp::Gates, 184
qpp::internal::IOManipRange, 206	TFQ
set	qpp, 112

qpp::QCircuitDescription, 297 TOF	qpp::exception::NotBipartite, 248 qpp::exception::NotImplemented, 250 qpp::exception::NotQubitCvector, 252 qpp::exception::NotQubitMatrix, 254 qpp::exception::NotQubitRvector, 256 qpp::exception::NotQubitSubsys, 258 qpp::exception::NotQubitVector, 260 qpp::exception::NotQubitVector, 260 qpp::exception::OutOfRange, 262 qpp::exception::PermInvalid, 264 qpp::exception::PermMismatchDims, 266 qpp::exception::QuditAlreadyMeasured, 313 qpp::exception::SizeMismatch, 323 qpp::exception::SubsysMismatchDims, 335 qpp::exception::TypeMismatch, 343 qpp::exception::UndefinedType, 345 qpp::exception::Unknown, 347 qpp::exception::ZeroSize, 352
qpp::QCircuitDescription, 298	types.h, 388
to_string qpp::Dynamic_bitset, 164 to_void	uniform qpp, 114
qpp, 28 toc	V_
qpp::Timer, 340 trace	<pre>qpp::Dynamic_bitset, 165 value_type</pre>
qpp, 112	qpp::Dynamic_bitset, 157
traits.h, 387	qpp::QCircuitDescription::iterator, 214
transpose	value_type_ qpp::QCircuitDescription::iterator::value_type_←
qpp, 113	, 348
tsallis	value_type_qcd_
qpp, 113, 114 Type	<pre>qpp::QCircuitDescription::iterator::value_type_←</pre>
qpp::Codes, 135	var
type qpp::make void, 218	qpp, 115
type_	variadic_vector_emplace
dpp::QCircuitDescription::iterator::value_type_← , 350	qpp::internal, 124
type_description	W
qpp::exception::CustomException, 139	qpp::States, 332 what
qpp::exception::DimsInvalid, 141	qpp::exception::Exception, 169
qpp::exception::DimsMismatchCvector, 143	what_
qpp::exception::DimsMismatchMatrix, 145	qpp::exception::CustomException, 139
<pre>qpp::exception::DimsMismatchRvector, 147 qpp::exception::DimsMismatchVector, 149</pre>	where_
qpp::exception::DimsNotEqual, 151	qpp::exception::Exception, 170
qpp::exception::Duplicates, 154	X
qpp::exception::Exception, 169	qpp::Bit_circuit, 133
qpp::exception::InvalidIterator, 197	qpp::Bit_circuit::Gate_count, 171
qpp::exception::MatrixMismatchSubsys, 220	qpp::Gates, 184
app::exception::MatrixNotCvector, 222	x0
<pre>qpp::exception::MatrixNotRvector, 224 qpp::exception::MatrixNotSquare, 226</pre>	qpp::States, 332 x1
qpp::exception::MatrixNotSquare, 220 qpp::exception::MatrixNotSquareNorCvector, 228	qpp::States, 333
qpp::exception::MatrixNotSquareNorRvector, 230	x2contfrac
qpp::exception::MatrixNotSquareNorVector, 232	qpp, 115
qpp::exception::MatrixNotVector, 234	Xd
qpp::exception::NoCodeword, 239	qpp::Gates, 182

```
Υ
    qpp::Gates, 185
y0
    qpp::States, 333
y1
    qpp::States, 333
Ζ
    qpp::Gates, 185
z0
    qpp::States, 333
z1
    qpp::States, 333
Zd
    qpp::Gates, 182
zero
    qpp::States, 329
```