Quantum++ v1.1

Generated by Doxygen 1.8.14

Contents

1	Qua	ntum++															1
2	Nam	nespace	Index														3
	2.1	Names	space List					 	 	 	 		 	 	 		 3
3	Hier	archica	l Index														5
	3.1	Class	Hierarchy					 	 	 	 		 	 	 		 5
4	Clas	s Index															7
	4.1	Class	List					 	 	 	 		 	 	 		 7
5	File	Index															11
	5.1	File Lis	st					 	 	 	 		 	 	 		 11
6	Nam	nespace	Docume	nta	tion												13
	6.1	qpp Na	amespace	Re	ferer	nce .		 	 	 	 		 	 	 		 13
		6.1.1	Detailed	De	scrip	tion		 	 	 	 		 	 	 		 26
		6.1.2	Typedef	Dod	cume	entati	on .	 	 	 	 		 	 	 		 26
			6.1.2.1	bi	igint			 	 	 	 		 	 	 		 26
			6.1.2.2	bı	ra .			 	 	 	 		 	 	 		 26
			6.1.2.3	CI	mat			 	 	 	 		 	 	 		 27
			6.1.2.4	c	plx .			 	 	 	 		 	 	 		 27
			6.1.2.5	dı	mat			 	 	 	 		 		 		 27
			6.1.2.6	dy	yn_c	ol_ve	ect .	 	 	 	 		 		 		 27
			6.1.2.7	dy	yn_m	nat .		 	 	 	 		 	 	 		 27
			6.1.2.8	d١	vn ro	ow v	ect		 	 	 		 	 	 		 28

ii CONTENTS

	6.1.2.9	idx	28
	6.1.2.10	ket	28
	6.1.2.11	to_void	28
6.1.3	Function	Documentation	28
	6.1.3.1	absm()	28
	6.1.3.2	abssq() [1/3]	29
	6.1.3.3	abssq() [2/3]	29
	6.1.3.4	abssq() [3/3]	30
	6.1.3.5	adjoint()	30
	6.1.3.6	anticomm()	30
	6.1.3.7	apply() [1/5]	31
	6.1.3.8	apply() [2/5]	31
	6.1.3.9	apply() [3/5]	32
	6.1.3.10	apply() [4/5]	32
	6.1.3.11	apply() [5/5]	33
	6.1.3.12	applyCTRL() [1/2]	33
	6.1.3.13	applyCTRL() [2/2]	34
	6.1.3.14	applyQFT()	35
	6.1.3.15	applyTFQ()	35
	6.1.3.16	avg()	36
	6.1.3.17	bloch2rho()	36
	6.1.3.18	choi2kraus()	37
	6.1.3.19	choi2super()	37
	6.1.3.20	comm()	38
	6.1.3.21	complement()	38
	6.1.3.22	compperm()	38
	6.1.3.23	concurrence()	40
	6.1.3.24	conjugate()	40
	6.1.3.25	contfrac2x()	41
	6.1.3.26	convergents() [1/2]	41

6.1.3.27	convergents() [2/2]	42
6.1.3.28	cor()	42
6.1.3.29	cosm()	43
6.1.3.30	cov()	43
6.1.3.31	cwise()	43
6.1.3.32	det()	44
6.1.3.33	dirsum() [1/4]	44
6.1.3.34	dirsum() [2/4]	45
6.1.3.35	dirsum() [3/4]	45
6.1.3.36	dirsum() [4/4]	46
6.1.3.37	dirsumpow()	46
6.1.3.38	disp() [1/5]	47
6.1.3.39	disp() [2/5]	47
6.1.3.40	disp() [3/5]	47
6.1.3.41	disp() [4/5]	48
6.1.3.42	disp() [5/5]	48
6.1.3.43	egcd()	49
6.1.3.44	eig()	49
6.1.3.45	entanglement() [1/2]	50
6.1.3.46	entanglement() [2/2]	50
6.1.3.47	entropy() [1/2]	51
6.1.3.48	entropy() [2/2]	51
6.1.3.49	evals()	52
6.1.3.50	evects()	52
6.1.3.51	expm()	52
6.1.3.52	factors()	53
6.1.3.53	funm()	53
6.1.3.54	gcd() [1/2]	54
6.1.3.55	gcd() [2/2]	54
6.1.3.56	gconcurrence()	55

iv CONTENTS

6.1.3.57	grams() [1/3]	55
6.1.3.58	grams() [2/3]	55
6.1.3.59	grams() [3/3]	56
6.1.3.60	hash_eigen_expression()	56
6.1.3.61	heig()	57
6.1.3.62	hevals()	57
6.1.3.63	hevects()	58
6.1.3.64	inverse()	58
6.1.3.65	invperm()	58
6.1.3.66	ip() [1/2]	59
6.1.3.67	ip() [2/2]	59
6.1.3.68	isprime()	60
6.1.3.69	kraus2choi()	60
6.1.3.70	kraus2super()	61
6.1.3.71	kron() [1/4]	61
6.1.3.72	kron() [2/4]	62
6.1.3.73	kron() [3/4]	62
6.1.3.74	kron() [4/4]	63
6.1.3.75	kronpow()	63
6.1.3.76	lcm() [1/2]	64
6.1.3.77	lcm() [2/2]	64
6.1.3.78	load()	64
6.1.3.79	loadMATLAB() [1/2]	65
6.1.3.80	loadMATLAB() [2/2]	66
6.1.3.81	logdet()	66
6.1.3.82	logm()	67
6.1.3.83	lognegativity() [1/2]	67
6.1.3.84	lognegativity() [2/2]	68
6.1.3.85	marginalX()	68
6.1.3.86	marginalY()	68

6.1.3.87 measure() [1/9]
6.1.3.88 measure() [2/9]
6.1.3.89 measure() [3/9]
6.1.3.90 measure() [4/9]
6.1.3.91 measure() [5/9]
6.1.3.92 measure() [6/9]
6.1.3.93 measure() [7/9]
6.1.3.94 measure() [8/9]
6.1.3.95 measure() [9/9]
6.1.3.96 measure_seq() [1/2]
6.1.3.97 measure_seq() [2/2]
6.1.3.98 mket() [1/2]
6.1.3.99 mket() [2/2]
6.1.3.100 modinv()
6.1.3.101 modmul()
6.1.3.102 modpow()
6.1.3.103 mprj() [1/2]
6.1.3.104 mprj() [2/2]
6.1.3.105 multiidx2n()
6.1.3.106 n2multiidx()
6.1.3.107 negativity() [1/2]
6.1.3.108 negativity() [2/2]
6.1.3.109 norm()
6.1.3.110 normalize()
6.1.3.111 omega()
6.1.3.112 operator""""_i()
6.1.3.113 powm()
6.1.3.114 prj()
6.1.3.115 prod() [1/3]
6.1.3.116 prod() [2/3]

vi

6.1.3.117 prod() [3/3]	84
6.1.3.118 ptrace() [1/2]	84
6.1.3.119 ptrace() [2/2]	85
6.1.3.120 ptrace1() [1/2]	85
6.1.3.121 ptrace1() [2/2]	86
6.1.3.122 ptrace2() [1/2]	86
6.1.3.123 ptrace2() [2/2]	87
6.1.3.124 ptranspose() [1/2]	87
6.1.3.125 ptranspose() [2/2]	88
6.1.3.126 QFT()	88
6.1.3.127 qmutualinfo() [1/2]	89
6.1.3.128 qmutualinfo() [2/2]	89
6.1.3.129 rand() [1/5]	90
6.1.3.130 rand() [2/5]	90
6.1.3.131 rand() [3/5]	91
6.1.3.132 rand() [4/5]	91
6.1.3.133 rand() [5/5]	92
6.1.3.134 randH()	92
6.1.3.135 randidx()	93
6.1.3.136 randket()	93
6.1.3.137 randkraus()	93
6.1.3.138 randn() [1/4]	94
6.1.3.139 randn() [2/4]	94
6.1.3.140 randn() [3/4]	95
6.1.3.141 randn() [4/4]	95
6.1.3.142 randperm()	96
6.1.3.143 randprime()	96
6.1.3.144 randprob()	97
6.1.3.145 randrho()	97
6.1.3.146 randU()	97

CONTENTS vii

6.1.3.147 randV()
6.1.3.148 renyi() [1/2]
6.1.3.149 renyi() [2/2]
6.1.3.150 reshape()
6.1.3.151 rho2bloch()
6.1.3.152 rho2pure()
6.1.3.153 save()
6.1.3.154 saveMATLAB() [1/2]
6.1.3.155 saveMATLAB() [2/2]
6.1.3.156 schatten()
6.1.3.157 schmidtA() [1/2]
6.1.3.158 schmidtA() [2/2]
6.1.3.159 schmidtB() [1/2]
6.1.3.160 schmidtB() [2/2]
6.1.3.161 schmidtcoeffs() [1/2]
6.1.3.162 schmidtcoeffs() [2/2]
6.1.3.163 schmidtprobs() [1/2]
6.1.3.164 schmidtprobs() [2/2]
6.1.3.165 sigma()
6.1.3.166 sinm()
6.1.3.167 spectralpowm()
6.1.3.168 sqrtm()
6.1.3.169 sum() [1/3]
6.1.3.170 sum() [2/3]
6.1.3.171 sum() [3/3]
6.1.3.172 super2choi()
6.1.3.173 svals()
6.1.3.174 svd()
6.1.3.175 svdU()
6.1.3.176 svdV()

viii CONTENTS

		6.1.3.177	syspermute() [1/2]	 	 	111
		6.1.3.178	syspermute() [2/2]	 	 	112
		6.1.3.179	TFQ()	 	 	112
		6.1.3.180	trace()	 	 	113
		6.1.3.181	transpose()	 	 	113
		6.1.3.182	tsallis() [1/2]	 	 	113
		6.1.3.183	tsallis() [2/2]	 	 	114
		6.1.3.184	uniform()	 	 	114
		6.1.3.185	var()	 	 	115
		6.1.3.186	x2contfrac()	 	 	115
	6.1.4	Variable	Occumentation	 	 	116
		6.1.4.1	chop	 	 	116
		6.1.4.2	ee	 	 	116
		6.1.4.3	infty	 	 	116
		6.1.4.4	maxn	 	 	116
		6.1.4.5	pi	 	 	116
6.2	qpp::ex	ception N	mespace Reference	 	 	116
	6.2.1	Detailed	Description	 	 	118
6.3	qpp::ex	perimenta	Namespace Reference	 	 	118
	6.3.1	Detailed	Description	 	 	118
6.4	qpp::int	ternal Nan	espace Reference	 	 	118
	6.4.1	Detailed	Description	 	 	120
	6.4.2	Function	Documentation	 	 	120
		6.4.2.1	check_cvector()	 	 	120
		6.4.2.2	check_dims()	 	 	120
		6.4.2.3	check_dims_match_cvect()	 	 	120
		6.4.2.4	check_dims_match_mat()	 	 	120
		6.4.2.5	check_dims_match_rvect()	 	 	121
		6.4.2.6	check_eq_dims()	 	 	121
		6.4.2.7	check_matching_sizes()	 	 	121

		6.4.2.8	check_no_duplicates()	21
		6.4.2.9	check_nonzero_size()	21
		6.4.2.10	check_perm()	21
		6.4.2.11	check_qubit_cvector()	22
		6.4.2.12	check_qubit_matrix()	22
		6.4.2.13	check_qubit_rvector()	22
		6.4.2.14	check_qubit_vector()	22
		6.4.2.15	check_rvector()	22
		6.4.2.16	check_square_mat()	22
		6.4.2.17	check_subsys_match_dims()	23
		6.4.2.18	check_vector()	23
		6.4.2.19	dirsum2()	23
		6.4.2.20	get_dim_subsys()	23
		6.4.2.21	get_num_subsys()	23
		6.4.2.22	hash_combine()	23
		6.4.2.23	kron2()	24
		6.4.2.24	multiidx2n()	24
		6.4.2.25	n2multiidx()	24
		6.4.2.26	variadic_vector_emplace() [1/2]	24
		6.4.2.27	variadic_vector_emplace() [2/2]	24
6.5	qpp::lit	erals Nam	espace Reference	25
	6.5.1	Function	Documentation	25
		6.5.1.1	operator""""_bra()	25
		6.5.1.2	operator""""_i()	25
		6.5.1.3	operator"""" _ket()	26
		6.5.1.4	operator""""_prj()	26

7	Clas	s Docu	mentation	129
	7.1	qpp::Bi	t_circuit Class Reference	129
		7.1.1	Detailed Description	131
		7.1.2	Constructor & Destructor Documentation	131
			7.1.2.1 Bit_circuit()	131
		7.1.3	Member Function Documentation	131
			7.1.3.1 CNOT()	131
			7.1.3.2 Dynamic_bitset()	132
			7.1.3.3 FRED()	132
			7.1.3.4 NOT()	132
			7.1.3.5 reset()	133
			7.1.3.6 SWAP()	133
			7.1.3.7 TOF()	133
			7.1.3.8 X()	134
		7.1.4	Member Data Documentation	134
			7.1.4.1 gate_count	134
	7.2	qpp::C	odes Class Reference	134
		7.2.1	Detailed Description	135
		7.2.2	Member Enumeration Documentation	135
			7.2.2.1 Type	136
		7.2.3	Constructor & Destructor Documentation	136
			7.2.3.1 Codes()	136
			7.2.3.2 ~Codes()	136
		7.2.4	Member Function Documentation	136
			7.2.4.1 codeword()	136
		7.2.5	Friends And Related Function Documentation	137
			7.2.5.1 internal::Singleton < const Codes >	137
	7.3	qpp::ex	cception::CustomException Class Reference	137
		7.3.1	Detailed Description	138
		7.3.2	Constructor & Destructor Documentation	138

CONTENTS xi

		7.3.2.1	CustomException()	. 139
	7.3.3	Member F	Function Documentation	. 139
		7.3.3.1	type_description()	. 139
	7.3.4	Member [Data Documentation	. 139
		7.3.4.1	what	. 139
7.4	qpp::ex	xception::D	imsInvalid Class Reference	. 140
	7.4.1	Detailed [Description	. 141
	7.4.2	Member F	Function Documentation	. 141
		7.4.2.1	Exception()	. 141
		7.4.2.2	type_description()	. 141
7.5	qpp::ex	xception::D	imsMismatchCvector Class Reference	. 142
	7.5.1	Detailed [Description	. 143
	7.5.2	Member F	Function Documentation	. 143
		7.5.2.1	Exception()	. 143
		7.5.2.2	type_description()	. 143
7.6	qpp::ex	xception::D	imsMismatchMatrix Class Reference	. 144
	7.6.1	Detailed [Description	. 145
	7.6.2	Member F	Function Documentation	. 145
		7.6.2.1	Exception()	. 145
		7.6.2.2	type_description()	. 145
7.7	qpp::ex	xception::D	imsMismatchRvector Class Reference	. 146
	7.7.1	Detailed [Description	. 147
	7.7.2	Member F	Function Documentation	. 147
		7.7.2.1	Exception()	. 147
		7.7.2.2	type_description()	. 147
7.8	qpp::ex	xception::D	imsMismatchVector Class Reference	. 148
	7.8.1	Detailed [Description	. 149
	7.8.2	Member F	Function Documentation	. 149
		7.8.2.1	Exception()	. 149
		7.8.2.2	type_description()	. 149

xii CONTENTS

7.9	qpp::ex	cception::DimsNotEqual Class Reference
	7.9.1	Detailed Description
	7.9.2	Member Function Documentation
		7.9.2.1 Exception()
		7.9.2.2 type_description()
7.10	qpp::in	ternal::Display_Impl_ Struct Reference
	7.10.1	Member Function Documentation
		7.10.1.1 display_impl_()
7.11	qpp::ex	cception::Duplicates Class Reference
	7.11.1	Detailed Description
	7.11.2	Member Function Documentation
		7.11.2.1 Exception()
		7.11.2.2 type_description()
7.12	qpp::D	ynamic_bitset Class Reference
	7.12.1	Detailed Description
	7.12.2	Member Typedef Documentation
		7.12.2.1 storage_type
		7.12.2.2 value_type
	7.12.3	Constructor & Destructor Documentation
		7.12.3.1 Dynamic_bitset()
		7.12.3.2 ~Dynamic_bitset()
	7.12.4	Member Function Documentation
		7.12.4.1 all()
		7.12.4.2 any()
		7.12.4.3 count()
		7.12.4.4 data()
		7.12.4.5 display()
		7.12.4.6 flip() [1/2]
		7.12.4.7 flip() [2/2]
		7.12.4.8 get()

CONTENTS xiii

		7.12.4.9 index_()	60
		7.12.4.10 none()	61
		7.12.4.11 offset_()	61
		7.12.4.12 operator"!=()	61
		7.12.4.13 operator-()	62
		7.12.4.14 operator==()	62
		7.12.4.15 rand() [1/2]	62
		7.12.4.16 rand() [2/2]	63
		7.12.4.17 reset() [1/2]	63
		7.12.4.18 reset() [2/2]	63
		7.12.4.19 set() [1/2]	64
		7.12.4.20 set() [2/2]	64
		7.12.4.21 size()	64
		7.12.4.22 storage_size()	64
		7.12.4.23 to_string()	65
	7.12.5	Member Data Documentation	65
		7.12.5.1 N	65
		7.12.5.2 storage_size	65
		7.12.5.3 v	66
7.13	qpp::ex	cception::Exception Class Reference	66
	7.13.1	Detailed Description	68
	7.13.2	Constructor & Destructor Documentation	69
		7.13.2.1 Exception()	69
	7.13.3	Member Function Documentation	69
		7.13.3.1 type_description()	69
		7.13.3.2 what()	70
	7.13.4	Member Data Documentation	70
		7.13.4.1 msg	70
		7.13.4.2 where	70
7.14	qpp::Bi	it_circuit::Gate_count Struct Reference	70

xiv CONTENTS

	7.14.1	Member Data Documentation
		7.14.1.1 CNOT
		7.14.1.2 FRED
		7.14.1.3 NOT
		7.14.1.4 SWAP
		7.14.1.5 TOF
		7.14.1.6 X
7.15	qpp::Ga	ates Class Reference
	7.15.1	Detailed Description
	7.15.2	Constructor & Destructor Documentation
		7.15.2.1 Gates()
		7.15.2.2 ~Gates()
	7.15.3	Member Function Documentation
		7.15.3.1 CTRL()
		7.15.3.2 expandout() [1/3]
		7.15.3.3 expandout() [2/3]
		7.15.3.4 expandout() [3/3]
		7.15.3.5 Fd()
		7.15.3.6 get_name()
		7.15.3.7 ld()
		7.15.3.8 MODMUL()
		7.15.3.9 Rn()
		7.15.3.10 RX()
		7.15.3.11 RY()
		7.15.3.12 RZ()
		7.15.3.13 SWAPd()
		7.15.3.14 Xd()
		7.15.3.15 Zd()
	7.15.4	Friends And Related Function Documentation
		7.15.4.1 internal::Singleton < const Gates >

CONTENTS xv

	7.15.5	Member Data Documentation
		7.15.5.1 CNOT
		7.15.5.2 CNOTba
		7.15.5.3 CZ
		7.15.5.4 FRED
		7.15.5.5 H
		7.15.5.6 ld2
		7.15.5.7 S
		7.15.5.8 SWAP
		7.15.5.9 T
		7.15.5.10 TOF
		7.15.5.11 X
		7.15.5.12 Y
		7.15.5.13 Z
7.16	qpp::Q0	Circuit::GateStep Struct Reference
	7.16.1	Detailed Description
	7.16.2	Constructor & Destructor Documentation
		7.16.2.1 GateStep() [1/2]
		7.16.2.2 GateStep() [2/2]
	7.16.3	Member Data Documentation
		7.16.3.1 ctrl
		7.16.3.2 gate
		7.16.3.3 gate_type
		7.16.3.4 name
		7.16.3.5 target
7.17	qpp::int	rernal::HashEigen Class Reference
	7.17.1	Detailed Description
	7.17.2	Member Function Documentation
		7.17.2.1 operator()()
7.18	qpp::ID	isplay Class Reference

xvi CONTENTS

	7.18.1	Detailed Description
	7.18.2	Constructor & Destructor Documentation
		7.18.2.1 IDisplay() [1/3]
		7.18.2.2 IDisplay() [2/3]
		7.18.2.3 IDisplay() [3/3]
		7.18.2.4 ~IDisplay()
	7.18.3	Member Function Documentation
		7.18.3.1 display()
		7.18.3.2 operator=() [1/2]
		7.18.3.3 operator=() [2/2]
	7.18.4	Friends And Related Function Documentation
		7.18.4.1 operator <<
7.19	qpp::IJ	SON Class Reference
	7.19.1	Detailed Description
	7.19.2	Constructor & Destructor Documentation
		7.19.2.1 IJSON() [1/3]
		7.19.2.2 IJSON() [2/3]
		7.19.2.3 IJSON() [3/3]
		7.19.2.4 ~IJSON()
	7.19.3	Member Function Documentation
		7.19.3.1 operator=() [1/2]
		7.19.3.2 operator=() [2/2]
		7.19.3.3 to_JSON()
7.20	qpp::Ini	t Class Reference
	7.20.1	Detailed Description
	7.20.2	Constructor & Destructor Documentation
		7.20.2.1 Init()
		7.20.2.2 ~Init()
	7.20.3	Friends And Related Function Documentation
		7.20.3.1 internal::Singleton < const Init >

CONTENTS xvii

7.21	qpp::ex	cception::InvalidIterator Class Reference	196
	7.21.1	Detailed Description	197
	7.21.2	Member Function Documentation	197
		7.21.2.1 Exception()	197
		7.21.2.2 type_description()	197
7.22	qpp::int	ternal::IOManipEigen Class Reference	198
	7.22.1	Constructor & Destructor Documentation	199
		7.22.1.1 IOManipEigen() [1/2]	199
		7.22.1.2 IOManipEigen() [2/2]	199
	7.22.2	Member Function Documentation	199
		7.22.2.1 display()	199
	7.22.3	Member Data Documentation	199
		7.22.3.1 A	200
		7.22.3.2 chop	200
7.23	qpp::int	ternal::IOManipPointer< PointerType > Class Template Reference	200
	7.23.1	Constructor & Destructor Documentation	201
		7.23.1.1 IOManipPointer() [1/2]	202
		7.23.1.2 IOManipPointer() [2/2]	202
	7.23.2	Member Function Documentation	202
		7.23.2.1 display()	202
		7.23.2.2 operator=()	202
	7.23.3	Member Data Documentation	202
		7.23.3.1 end	203
		7.23.3.2 N	203
		7.23.3.3 p	203
		7.23.3.4 separator	203
		7.23.3.5 start	203
7.24	qpp::int	ternal::IOManipRange< InputIterator > Class Template Reference	204
	7.24.1	Constructor & Destructor Documentation	205
		7.24.1.1 IOManipRange() [1/2]	205

xviii CONTENTS

		7.24.1.2 IOManipRange() [2/2]	205
	7.24.2	Member Function Documentation	205
		7.24.2.1 display()	205
		7.24.2.2 operator=()	206
	7.24.3	Member Data Documentation	206
		7.24.3.1 end	206
		7.24.3.2 first	206
		7.24.3.3 last	206
		7.24.3.4 separator	206
		7.24.3.5 start	206
7.25	qpp::is_	_complex< T > Struct Template Reference	207
	7.25.1	Detailed Description	207
7.26	qpp::is_	_complex< std::complex< T > > Struct Template Reference	208
	7.26.1	Detailed Description	208
7.27	qpp::is_	_iterable < T, typename > Struct Template Reference	209
	7.27.1	Detailed Description	209
7.28		_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T d()), decltype(*(std::declval < T >().begin())) > Struct Template Reference	210
	7.28.1	Detailed Description	211
7.29	qpp::is_	_matrix_expression< Derived > Struct Template Reference	211
	7.29.1	Detailed Description	211
7.30	qpp::Q	Circuit::iterator Class Reference	212
	7.30.1	Detailed Description	213
	7.30.2	Member Typedef Documentation	213
		7.30.2.1 difference_type	213
		7.30.2.2 iterator_category	213
		7.30.2.3 pointer	214
		7.30.2.4 reference	214
		7.30.2.5 value_type	214
	7.30.3	Constructor & Destructor Documentation	214
		7.30.3.1 iterator() [1/2]	214

CONTENTS xix

		7.30.3.2 iterator() [2/2]	<u>'</u> 14
	7.30.4	Member Function Documentation	214
		7.30.4.1 operator"!=()	214
		7.30.4.2 operator*()	15
		7.30.4.3 operator++() [1/2]	15
		7.30.4.4 operator++() [2/2]	15
		7.30.4.5 operator=()	16
		7.30.4.6 operator==()	16
		7.30.4.7 set_begin_()	16
		7.30.4.8 set_end_()	16
	7.30.5	Member Data Documentation	17
		7.30.5.1 elem	17
		7.30.5.2 qc	17
7.31	qpp::int	ternal::KeyEqualEigen Class Reference	17
	7.31.1	Detailed Description	17
	7.31.2	Member Function Documentation	18
		7.31.2.1 operator()()	18
7.32	qpp::ma	ake_void < Ts > Struct Template Reference	18
	7.32.1	Detailed Description	18
	7.32.2	Member Typedef Documentation	18
		7.32.2.1 type	18
7.33	qpp::ex	cception::MatrixMismatchSubsys Class Reference	19
	7.33.1	Detailed Description	220
	7.33.2	Member Function Documentation	220
		7.33.2.1 Exception()	220
		7.33.2.2 type_description()	220
7.34	qpp::ex	cception::MatrixNotCvector Class Reference	21
	7.34.1	Detailed Description	222
	7.34.2	Member Function Documentation	222
		7.34.2.1 Exception()	222

		7.34.2.2 type_description()	222
7.35	qpp::ex	cception::MatrixNotRvector Class Reference	223
	7.35.1	Detailed Description	224
	7.35.2	Member Function Documentation	224
		7.35.2.1 Exception()	224
		7.35.2.2 type_description()	224
7.36	qpp::ex	cception::MatrixNotSquare Class Reference	225
	7.36.1	Detailed Description	226
	7.36.2	Member Function Documentation	226
		7.36.2.1 Exception()	226
		7.36.2.2 type_description()	226
7.37	qpp::ex	cception::MatrixNotSquareNorCvector Class Reference	227
	7.37.1	Detailed Description	228
	7.37.2	Member Function Documentation	228
		7.37.2.1 Exception()	228
		7.37.2.2 type_description()	228
7.38	qpp::ex	cception::MatrixNotSquareNorRvector Class Reference	229
	7.38.1	Detailed Description	230
	7.38.2	Member Function Documentation	230
		7.38.2.1 Exception()	230
		7.38.2.2 type_description()	230
7.39	qpp::ex	cception::MatrixNotSquareNorVector Class Reference	231
	7.39.1	Detailed Description	232
	7.39.2	Member Function Documentation	232
		7.39.2.1 Exception()	232
		7.39.2.2 type_description()	232
7.40	qpp::ex	cception::MatrixNotVector Class Reference	233
	7.40.1	Detailed Description	234
	7.40.2	Member Function Documentation	234
		7.40.2.1 Exception()	234

CONTENTS xxi

		7.40.2.2 type_description()
7.41	qpp::Q	Circuit::MeasureStep Struct Reference
	7.41.1	Detailed Description
	7.41.2	Constructor & Destructor Documentation
		7.41.2.1 MeasureStep() [1/2]
		7.41.2.2 MeasureStep() [2/2]
	7.41.3	Member Data Documentation
		7.41.3.1 c_reg
		7.41.3.2 mats
		7.41.3.3 measurement_type
		7.41.3.4 name
		7.41.3.5 target
7.42	qpp::ex	cception::NoCodeword Class Reference
	7.42.1	Detailed Description
	7.42.2	Member Function Documentation
		7.42.2.1 Exception()
		7.42.2.2 type_description()
7.43	qpp::No	oiseBase< T > Class Template Reference
	7.43.1	Detailed Description
	7.43.2	Member Typedef Documentation
		7.43.2.1 noise_type
	7.43.3	Constructor & Destructor Documentation
		7.43.3.1 NoiseBase() [1/2]
		7.43.3.2 NoiseBase() [2/2]
		7.43.3.3 ~NoiseBase()
	7.43.4	Member Function Documentation
		7.43.4.1 compute_probs_()
		7.43.4.2 compute_state_()
		7.43.4.3 get_d()
		7.43.4.4 get_Ks()

xxii CONTENTS

		7.43.4.5 get_last_idx()	14
		7.43.4.6 get_last_K()	14
		7.43.4.7 get_last_p()	14
		7.43.4.8 get_probs()	14
		7.43.4.9 operator()() [1/2]	14
		7.43.4.10 operator()() [2/2]	1 5
	7.43.5	Member Data Documentation	1 5
		7.43.5.1 d	1 5
		7.43.5.2 generated	1 5
		7.43.5.3 i	1 6
		7.43.5.4 Ks	1 6
		7.43.5.5 probs	1 6
7.44	qpp::No	piseType Class Reference	1 6
	7.44.1	Detailed Description	1 6
7.45	qpp::ex	cception::NotBipartite Class Reference	1 7
	7.45.1	Detailed Description	1 8
	7.45.2	Member Function Documentation	1 8
		7.45.2.1 Exception()	1 8
		7.45.2.2 type_description()	1 8
7.46	qpp::ex	cception::NotImplemented Class Reference	1 9
	7.46.1	Detailed Description	50
	7.46.2	Member Function Documentation	50
		7.46.2.1 Exception()	50
		7.46.2.2 type_description()	50
7.47	qpp::ex	cception::NotQubitCvector Class Reference	51
	7.47.1	Detailed Description	52
	7.47.2	Member Function Documentation	52
		7.47.2.1 Exception()	52
		7.47.2.2 type_description()	52
7.48	qpp::ex	cception::NotQubitMatrix Class Reference	53

CONTENTS xxiii

	7.48.1	Detailed Description	54
	7.48.2	Member Function Documentation	54
		7.48.2.1 Exception()	54
		7.48.2.2 type_description()	54
7.49	qpp::ex	cception::NotQubitRvector Class Reference	55
	7.49.1	Detailed Description	56
	7.49.2	Member Function Documentation	56
		7.49.2.1 Exception()	56
		7.49.2.2 type_description()	56
7.50	qpp::ex	cception::NotQubitSubsys Class Reference	57
	7.50.1	Detailed Description	58
	7.50.2	Member Function Documentation	58
		7.50.2.1 Exception()	58
		7.50.2.2 type_description()	58
7.51	qpp::ex	cception::NotQubitVector Class Reference	59
	7.51.1	Detailed Description	30
	7.51.2	Member Function Documentation	30
		7.51.2.1 Exception()	30
		7.51.2.2 type_description()	60
7.52	qpp::ex	cception::OutOfRange Class Reference	61
	7.52.1	Detailed Description	62
		Member Function Documentation	
		7.52.2.1 Exception()	
		7.52.2.2 type_description()	
7 53	annex	cception::PermInvalid Class Reference	
7.00		Detailed Description	
		Member Function Documentation	
	1.00.2		
		7.53.2.1 Exception()	
		7.53.2.2 type_description()	
7.54	qpp::ex	cception::PermMismatchDims Class Reference	<i>i</i> 5

xxiv CONTENTS

	7.54.1	Detailed Description
	7.54.2	Member Function Documentation
		7.54.2.1 Exception()
		7.54.2.2 type_description()
7.55	qpp::Q0	Circuit Class Reference
	7.55.1	Detailed Description
	7.55.2	Member Typedef Documentation
		7.55.2.1 const_iterator
	7.55.3	Member Enumeration Documentation
		7.55.3.1 GateType
		7.55.3.2 MeasureType
		7.55.3.3 StepType
	7.55.4	Constructor & Destructor Documentation
		7.55.4.1 QCircuit()
		7.55.4.2 ~QCircuit()
	7.55.5	Member Function Documentation
		7.55.5.1 begin() [1/2]
		7.55.5.2 begin() [2/2]
		7.55.5.3 cbegin()
		7.55.5.4 cCTRL() [1/4]
		7.55.5.5 cCTRL() [2/4]
		7.55.5.6 cCTRL() [3/4]
		7.55.5.7 cCTRL() [4/4]
		7.55.5.8 cCTRL_custom()
		7.55.5.9 cend()
		7.55.5.10 CTRL() [1/4]
		7.55.5.11 CTRL() [2/4]
		7.55.5.12 CTRL() [3/4]
		7.55.5.13 CTRL() [4/4]
		7.55.5.14 CTRL_custom()

CONTENTS xxv

7.55.5.15 display()
7.55.5.16 end() [1/2]
7.55.5.17 end() [2/2]
7.55.5.18 gate() [1/3]
7.55.5.19 gate() [2/3]
7.55.5.20 gate() [3/3]
7.55.5.21 gate_custom()
7.55.5.22 gate_fan() [1/3]
7.55.5.23 gate_fan() [2/3]
7.55.5.24 gate_fan() [3/3]
7.55.5.25 get_d()
7.55.5.26 get_gate_count() [1/2]
7.55.5.27 get_gate_count() [2/2]
7.55.5.28 get_gate_depth() [1/2]
7.55.5.29 get_gate_depth() [2/2]
7.55.5.30 get_gates_()
7.55.5.31 get_measured() [1/2]
7.55.5.32 get_measured() [2/2]
7.55.5.33 get_measurement_count() [1/2]
7.55.5.34 get_measurement_count() [2/2]
7.55.5.35 get_measurements_()
7.55.5.36 get_name()
7.55.5.37 get_nc()
7.55.5.38 get_non_measured()
7.55.5.39 get_nq()
7.55.5.40 get_step_count()
7.55.5.41 measureV() [1/2]
7.55.5.42 measureV() [2/2]
7.55.5.43 measureZ()
7.55.5.44 QFT()

xxvi CONTENTS

		7.55.5.45 TFQ()	:89
		7.55.5.46 to_JSON()	:89
	7.55.6	Friends And Related Function Documentation	:90
		7.55.6.1 operator << [1/4]	:90
		7.55.6.2 operator << [2/4]	90
		7.55.6.3 operator << [3/4]	91
		7.55.6.4 operator << [4/4]	91
		7.55.6.5 QEngine	91
	7.55.7	Member Data Documentation	92
		7.55.7.1 count	92
		7.55.7.2 d	:92
		7.55.7.3 depth	:92
		7.55.7.4 gates	:92
		7.55.7.5 measured	:92
		7.55.7.6 measurement_count	:93
		7.55.7.7 measurements	:93
		7.55.7.8 name	:93
		7.55.7.9 nc	:93
		7.55.7.10 nq	:93
		7.55.7.11 step_types	:93
7.56	qpp::Ql	Engine Class Reference	94
	7.56.1	Detailed Description	:96
	7.56.2	Constructor & Destructor Documentation	:96
		7.56.2.1 QEngine() [1/3]	:96
		7.56.2.2 QEngine() [2/3]	296
		7.56.2.3 QEngine() [3/3]	97
		7.56.2.4 ~QEngine()	97
	7.56.3	Member Function Documentation	:97
		7.56.3.1 display()	:97
		7.56.3.2 execute() [1/2]	:97

CONTENTS xxvii

	7.56.3.3 execute() [2/2]	290
	7.56.3.4 get_circuit()	298
	7.56.3.5 get_dit()	298
	7.56.3.6 get_dits()	299
	7.56.3.7 get_measured() [1/2]	299
	7.56.3.8 get_measured() [2/2]	299
	7.56.3.9 get_not_measured()	299
	7.56.3.10 get_probs()	300
	7.56.3.11 get_psi()	300
	7.56.3.12 get_ref_psi()	300
	7.56.3.13 get_relative_pos_()	300
	7.56.3.14 operator=()	301
	7.56.3.15 reset()	301
	7.56.3.16 set_dit()	301
	7.56.3.17 set_measured_()	302
	7.56.3.18 to_JSON()	302
7.56.4	Member Data Documentation	302
	7.56.4.1 dits	302
	7.56.4.2 probs	302
	7.56.4.3 psi	303
	7.56.4.4 qc	303
	7.56.4.5 subsys	303
qpp::Qı	bitAmplitudeDampingNoise Class Reference	303
7.57.1	Detailed Description	304
7.57.2	Constructor & Destructor Documentation	304
	7.57.2.1 QubitAmplitudeDampingNoise()	304
qpp::Qı	bitBitFlipNoise Class Reference	305
7.58.1	Detailed Description	306
7.58.2	Constructor & Destructor Documentation	306
	7.58.2.1 QubitBitFlipNoise()	306
	7.56.4 qpp::Qul 7.57.1 7.57.2 qpp::Qul 7.58.1 7.58.2	7.56.3.4 get_circuit() 7.56.3.5 get_dit() 7.56.3.5 get_dit() 7.56.3.6 get_dits() 7.56.3.7 get_measured() 11/21 7.56.3.8 get_measured() [2/2] 7.56.3.9 get_not_measured() 7.56.3.10 get_probs() 7.56.3.11 get_psi() 7.56.3.12 get_ref_psi() 7.56.3.13 get_relative_pos_() 7.56.3.14 operator=() 7.56.3.15 reset() 7.56.3.16 set_dit() 7.56.3.18 to_JSON() 7.56.4.1 dits_ 7.56.4.1 dits_ 7.56.4.2 probs_ 7.56.4.3 psi_ 7.56.4.4 qc_ 7.56.4.5 subsys_ qpp::QubitAmplitudeDampingNoise Class Reference 7.57.1 Detailed Description 7.57.2.1 QubitAmplitudeDampingNoise() qpp::QubitBitFlipNoise Class Reference 7.58.1 Detailed Description 7.58.1 Detailed Description 7.58.1 Detailed Description 7.58.1 Detailed Description

xxviii CONTENTS

7.59	qpp::Qı	ubitBitPhaseFlipNoise Class Reference	306
	7.59.1	Detailed Description	307
	7.59.2	Constructor & Destructor Documentation	307
		7.59.2.1 QubitBitPhaseFlipNoise()	307
7.60	qpp::Q	ubitDepolarizingNoise Class Reference	308
	7.60.1	Detailed Description	309
	7.60.2	Constructor & Destructor Documentation	309
		7.60.2.1 QubitDepolarizingNoise()	309
7.61	qpp::Qı	ubitPhaseDampingNoise Class Reference	309
	7.61.1	Detailed Description	310
	7.61.2	Constructor & Destructor Documentation	310
		7.61.2.1 QubitPhaseDampingNoise()	310
7.62	qpp::Q	ubitPhaseFlipNoise Class Reference	311
	7.62.1	Detailed Description	312
	7.62.2	Constructor & Destructor Documentation	312
		7.62.2.1 QubitPhaseFlipNoise()	312
7.63	qpp::ex	cception::QuditAlreadyMeasured Class Reference	312
	7.63.1	Detailed Description	313
	7.63.2	Member Function Documentation	313
		7.63.2.1 Exception()	313
		7.63.2.2 type_description()	314
7.64	qpp::Q	uditDepolarizingNoise Class Reference	314
	7.64.1	Detailed Description	315
	7.64.2	Constructor & Destructor Documentation	315
		7.64.2.1 QuditDepolarizingNoise()	315
	7.64.3	Member Function Documentation	316
		7.64.3.1 fill_Ks_()	316
		7.64.3.2 fill_probs_()	316
7.65	qpp::Ra	andomDevices Class Reference	317
	7.65.1	Detailed Description	318

CONTENTS xxix

	7.65.2	Constructor & Destructor Documentation
		7.65.2.1 RandomDevices()
		7.65.2.2 ~RandomDevices()
	7.65.3	Member Function Documentation
		7.65.3.1 get_prng()
		7.65.3.2 load()
		7.65.3.3 save()
	7.65.4	Friends And Related Function Documentation
		7.65.4.1 internal::Singleton < RandomDevices >
	7.65.5	Member Data Documentation
		7.65.5.1 prng
		7.65.5.2 rd
7.66	qpp::int	ternal::Singleton < T > Class Template Reference
	7.66.1	Detailed Description
	7.66.2	Constructor & Destructor Documentation
		7.66.2.1 Singleton() [1/2]
		7.66.2.2 Singleton() [2/2]
		7.66.2.3 ~Singleton()
	7.66.3	Member Function Documentation
		7.66.3.1 get_instance()
		7.66.3.2 get_thread_local_instance()
		7.66.3.3 operator=()
7.67	qpp::ex	cception::SizeMismatch Class Reference
	7.67.1	Detailed Description
	7.67.2	Member Function Documentation
		7.67.2.1 Exception()
		7.67.2.2 type_description()
7.68	qpp::No	piseType::StateDependent Class Reference
	7.68.1	Detailed Description
7.69	qpp::No	piseType::StateIndependent Class Reference

	7.69.1	Detailed Description	25
7.70	qpp::St	ates Class Reference	25
	7.70.1	Detailed Description	27
	7.70.2	Constructor & Destructor Documentation	28
		7.70.2.1 States()	28
		7.70.2.2 ~States()	28
	7.70.3	Member Function Documentation	28
		7.70.3.1 jn()	28
		7.70.3.2 mes()	28
		7.70.3.3 minus()	29
		7.70.3.4 one()	29
		7.70.3.5 plus()	30
		7.70.3.6 zero()	30
	7.70.4	Friends And Related Function Documentation	30
		7.70.4.1 internal::Singleton < const States >	30
	7.70.5	Member Data Documentation	30
		7.70.5.1 b00	31
		7.70.5.2 b01	31
		7.70.5.3 b10	31
		7.70.5.4 b11	31
		7.70.5.5 GHZ	31
		7.70.5.6 pb00	31
		7.70.5.7 pb01	32
		7.70.5.8 pb10	32
		7.70.5.9 pb11	32
		7.70.5.10 pGHZ	32
		7.70.5.11 pW	32
		7.70.5.12 px0	32
		7.70.5.404	33
		7.70.5.13 px1	
		7.70.5.13 px1	33

CONTENTS xxxi

	7.70.5.15 py1	333
	7.70.5.16 pz0	333
	7.70.5.17 pz1	333
	7.70.5.18 W	333
	7.70.5.19 x0	334
	7.70.5.20 x1	334
	7.70.5.21 y0	334
	7.70.5.22 y1	334
	7.70.5.23 z0	334
	7.70.5.24 z1	334
7.71 qpp::e	xception::SubsysMismatchDims Class Reference	335
7.71.1	Detailed Description	336
7.71.2	Member Function Documentation	336
	7.71.2.1 Exception()	336
	7.71.2.2 type_description()	336
7.72 qpp::T	imer< T, CLOCK_T > Class Template Reference	337
7.72.1	Detailed Description	338
7.72.2	Constructor & Destructor Documentation	338
	7.72.2.1 Timer() [1/3]	338
	7.72.2.2 Timer() [2/3]	339
	7.72.2.3 Timer() [3/3]	339
	7.72.2.4 ~Timer()	339
7.72.3	Member Function Documentation	339
	7.72.3.1 display()	339
	7.72.3.2 get_duration()	340
	7.72.3.3 operator=() [1/2]	340
	7.72.3.4 operator=() [2/2]	340
	7.72.3.5 tic()	341
	7.72.3.6 tics()	341

xxxii CONTENTS

	7.72.4	Member Data Documentation	41
		7.72.4.1 end	41
		7.72.4.2 start	42
7.73	qpp::ex	cception::TypeMismatch Class Reference	42
	7.73.1	Detailed Description	43
	7.73.2	Member Function Documentation	43
		7.73.2.1 Exception()	43
		7.73.2.2 type_description()	44
7.74	qpp::ex	cception::UndefinedType Class Reference	44
	7.74.1	Detailed Description	45
	7.74.2	Member Function Documentation	45
		7.74.2.1 Exception()	45
		7.74.2.2 type_description()	46
7.75	qpp::ex	cception::Unknown Class Reference	46
	7.75.1	Detailed Description	47
	7.75.2	Member Function Documentation	47
		7.75.2.1 Exception()	47
		7.75.2.2 type_description()	48
7.76	qpp::Q	Circuit::iterator::value_type_ Class Reference	48
	7.76.1	Constructor & Destructor Documentation	49
		7.76.1.1 value_type_() [1/2]	49
		7.76.1.2 value_type_() [2/2]	49
	7.76.2	Member Function Documentation	50
		7.76.2.1 display()	50
		7.76.2.2 operator=()	50
	7.76.3	Member Data Documentation	50
		7.76.3.1 gates_ip	50
		7.76.3.2 ip	51
		7.76.3.3 measurements_ip	51
		7.76.3.4 type	51
		7.76.3.5 value_type_qc	51
7.77	qpp::ex	cception::ZeroSize Class Reference	52
	7.77.1	Detailed Description	53
	7.77.2	Member Function Documentation	53
		7.77.2.1 Exception()	53
		7.77.2.2 type_description()	53

CONTENTS xxxiii

8	File I	Documentation	355
	8.1	classes/circuits.h File Reference	355
		8.1.1 Detailed Description	356
	8.2	classes/codes.h File Reference	356
		8.2.1 Detailed Description	356
	8.3	classes/exception.h File Reference	357
		8.3.1 Detailed Description	359
	8.4	classes/gates.h File Reference	359
		8.4.1 Detailed Description	359
	8.5	classes/idisplay.h File Reference	360
		8.5.1 Detailed Description	360
	8.6	classes/init.h File Reference	360
		8.6.1 Detailed Description	361
	8.7	classes/noise.h File Reference	361
		8.7.1 Detailed Description	362
	8.8	classes/random_devices.h File Reference	362
		8.8.1 Detailed Description	362
	8.9	classes/reversible.h File Reference	363
		8.9.1 Detailed Description	363
	8.10	classes/states.h File Reference	363
		8.10.1 Detailed Description	364
	8.11	classes/timer.h File Reference	364
		8.11.1 Detailed Description	365
	8.12	constants.h File Reference	365
		8.12.1 Detailed Description	366
	8.13	entanglement.h File Reference	366
		8.13.1 Detailed Description	368
	8.14	entropies.h File Reference	368
		8.14.1 Detailed Description	369
	8.15	experimental/experimental.h File Reference	369

	8.15.1 Detailed Description	369
8.16	functions.h File Reference	369
	8.16.1 Detailed Description	374
8.17	input_output.h File Reference	374
	8.17.1 Detailed Description	375
8.18	instruments.h File Reference	375
	8.18.1 Detailed Description	377
8.19	internal/classes/iomanip.h File Reference	377
	8.19.1 Detailed Description	377
8.20	internal/classes/singleton.h File Reference	378
	8.20.1 Detailed Description	378
8.21	internal/util.h File Reference	378
	8.21.1 Detailed Description	380
8.22	MATLAB/matlab.h File Reference	380
	8.22.1 Detailed Description	381
8.23	number_theory.h File Reference	381
	8.23.1 Detailed Description	382
8.24	operations.h File Reference	383
	8.24.1 Detailed Description	385
8.25	qpp.h File Reference	385
	8.25.1 Detailed Description	386
	8.25.2 Macro Definition Documentation	386
	8.25.2.1 QPP_UNUSED	386
8.26	random.h File Reference	387
	8.26.1 Detailed Description	388
8.27	statistics.h File Reference	388
	8.27.1 Detailed Description	389
8.28	traits.h File Reference	389
	8.28.1 Detailed Description	390
8.29	types.h File Reference	391
	8.29.1 Detailed Description	392
8.30	/Users/vlad/qpp/README.md File Reference	392

Index

393

Chapter 1

Quantum++

Version 1.1 - 26 November 2018

Build status:

Chat (questions/issues)

About

Quantum++ is a modern C++11 general purpose quantum computing library, composed solely of template header files. Quantum++ is written in standard C++11 and has very low external dependencies, using only the Eigen 3 linear algebra header-only template library and, if available, the OpenMP multi-processing library.

Quantum++ is not restricted to qubit systems or specific quantum information processing tasks, being capable of simulating arbitrary quantum processes. The main design factors taken in consideration were the ease of use, high portability, and high performance. The library's simulation capabilities are only restricted by the amount of available physical memory. On a typical machine (Intel i5 8Gb RAM) Quantum++ can successfully simulate the evolution of 25 qubits in a pure state or of 12 qubits in a mixed state reasonably fast.

To report any bugs or ask for additional features/enhancements, please submit an issue with an appropriate label.

If you are interesting in contributing to this project, feel free to contact me. Alternatively, create a custom branch, add your contribution, then finally create a pull request. If I accept the pull request, I will merge your custom branch with the latest development branch. The latter will eventually be merged into a future release version. To contribute, you need to have a solid knowledge of C++ (preferably C++11), including templates and the standard library, a basic knowledge of quantum computing and linear algebra, and working experience with Eigen 3.

For additional Eigen 3 documentation see http://eigen.tuxfamily.org/dox/. For a simple Eigen 3 quick ASCII reference see http://eigen.tuxfamily.org/dox/AsciiQuickReference.txt.

Copyright (c) 2013 - 2019 Vlad Gheorghiu, vgheorgh AT gmail DOT com.

License

Quantum++ is distributed under the MIT license. Please see the LICENSE file for more details.

Installation instructions and further documentation

Please see the installation guide https://github.com/vsoftco/qpp/blob/master/INSTALL.md "`INSTALL.md`" and the comprehensive Wiki for further documentation and detailed examples.

The official API documentation is available in PDF and HTML formats in the doc folder.

2 Quantum++

Chapter 2

Namespace Index

2.1 Namespace List

Here is a list of all namespaces with brief descriptions:

pp	
Quantum++ main namespace	13
p::exception	
Quantum++ exception hierarchy namespace	116
p::experimental	
Experimental/test functions/classes, do not use or modify	118
p::internal	
Internal utility functions, do not use them directly or modify them	118
p::literals	125

4 Namespace Index

Chapter 3

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

qpp::internal::Display_Impl
qpp::internal::IOManipEigen
std::exception
qpp::exception::Exception
qpp::exception::CustomException
qpp::exception::DimsInvalid
qpp::exception::DimsMismatchCvector
qpp::exception::DimsMismatchMatrix
qpp::exception::DimsMismatchRvector
qpp::exception::DimsMismatchVector
qpp::exception::DimsNotEqual
qpp::exception::Duplicates
qpp::exception::InvalidIterator
qpp::exception::MatrixMismatchSubsys
qpp::exception::MatrixNotCvector
qpp::exception::MatrixNotRvector
qpp::exception::MatrixNotSquare
qpp::exception::MatrixNotSquareNorCvector
qpp::exception::MatrixNotSquareNorRvector
qpp::exception::MatrixNotSquareNorVector
qpp::exception::MatrixNotVector
qpp::exception::NoCodeword
qpp::exception::NotBipartite
qpp::exception::NotImplemented
qpp::exception::NotQubitCvector
qpp::exception::NotQubitMatrix
qpp::exception::NotQubitRvector
qpp::exception::NotQubitSubsys
qpp::exception::NotQubitVector
qpp::exception::OutOfRange
qpp::exception::PermInvalid
qpp::exception::PermMismatchDims
qpp::exception::QuditAlreadyMeasured
qpp::exception::SizeMismatch
gpp::exception::SubsysMismatchDims

6 Hierarchical Index

qpp::exception::TypeMismatch	
qpp::exception::UndefinedType	
qpp::exception::Unknown	
qpp::exception::ZeroSize	352
false_type	
qpp::is_complex< T >	
qpp::is_iterable < T, typename >	
qpp::Bit_circuit::Gate_count	
qpp::QCircuit::GateStep	
qpp::internal::HashEigen	
qpp::IDisplay	
qpp::Dynamic_bitset	
qpp::Bit_circuit	
qpp::internal::IOManipEigen	
qpp::internal::IOManipPointer< PointerType >	
qpp::internal::IOManipRange< InputIterator >	
qpp::QCircuit	
qpp::QCircuit::iterator::value_type	
qpp::QEngine	
qpp::Timer< T, CLOCK_T >	
qpp::IJSON	
qpp::QCircuit	
qpp::QEngine	294
is_base_of	
qpp::is_matrix_expression< Derived >	211
qpp::QCircuit::iterator	. 212
qpp::internal::KeyEqualEigen	. 217
$qpp :: make_void < Ts > \ . \ . \ . \ . \ . \ . \ . \ . \ . \$. 218
qpp::QCircuit::MeasureStep	. 235
qpp::NoiseBase < T >	
qpp::NoiseBase < NoiseType::StateDependent >	. 239
qpp::QubitAmplitudeDampingNoise	
qpp::QubitPhaseDampingNoise	309
qpp:: Noise Base < Noise Type:: State Independent >	. 239
qpp::QubitBitFlipNoise	305
qpp::QubitBitPhaseFlipNoise	306
qpp::QubitDepolarizingNoise	308
qpp::QubitPhaseFlipNoise	311
qpp::QuditDepolarizingNoise	314
qpp::NoiseType	. 246
$qpp::internal::Singleton < T > \dots \dots$. 320
$qpp :: internal :: Singleton < const \ Codes > \dots $. 320
qpp::Codes	134
qpp::internal::Singleton < const Gates >	. 320
qpp::Gates	172
qpp::internal::Singleton< const Init >	
qpp::Init	
qpp::internal::Singleton < const States >	
qpp::States	
" '	
qpp::internal::Singleton < RandomDevices >	
qpp::RandomDevices	
qpp::NoiseType::StateDependent	
qpp::NoiseType::StateIndependent	. 325
true_type	00-
qpp::is_complex < std::complex < T >>	
<pre>app::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval< T)</pre>	
$> ().end()),\ decltype(*(std::declval < T > ().begin())) >> \ \dots $	210

Chapter 4

Class Index

4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

qpp::Bit_circuit	
Classical reversible circuit simulator	129
qpp::Codes	
Const Singleton class that defines quantum error correcting codes	134
qpp::exception::CustomException	
Custom exception	137
qpp::exception::DimsInvalid	
Invalid dimension(s) exception	140
qpp::exception::DimsMismatchCvector	
Dimension(s) mismatch column vector size exception	142
qpp::exception::DimsMismatchMatrix	
Dimension(s) mismatch matrix size exception	144
qpp::exception::DimsMismatchRvector	
Dimension(s) mismatch row vector size exception	146
qpp::exception::DimsMismatchVector	
Dimension(s) mismatch vector size exception	148
qpp::exception::DimsNotEqual	
Dimensions not equal exception	150
qpp::internal::Display_Impl	152
qpp::exception::Duplicates	
System (e.g. std::vector) has duplicates exception	153
qpp::Dynamic_bitset	
Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std←	
::bitset <n>)</n>	155
qpp::exception::Exception	
Base class for generating Quantum++ custom exceptions	166
qpp::Bit_circuit::Gate_count	170
qpp::Gates	
Const Singleton class that implements most commonly used gates	172
qpp::QCircuit::GateStep	
One step consisting only of gates/operators in the circuit	185
qpp::internal::HashEigen	
Functor for hashing Eigen expressions	188
qpp::IDisplay	
Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream	& os) c

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const 189

8 Class Index

qpp::IJSON	
Abstract class (interface) that mandates the definition of very basic JSON serialization support qpp::Init	192
Const Singleton class that performs additional initializations/cleanups	194
qpp::exception::InvalidIterator	400
Invalid iterator	
qpp::internal::IOManipEigen	
qpp::internal::IOManipPointer< PointerType >	
qpp::internal::IOManipRange< InputIterator >	204
qpp::is_complex< T >	
Checks whether the type is a complex type	207
qpp::is_complex< std::complex< T > >	
Checks whether the type is a complex number type, specialization for complex types	208
qpp::is_iterable < T, typename >	
Checks whether T is compatible with an STL-like iterable container $\dots \dots \dots \dots \dots$	
qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), one of the container is compatible with an STL-like iterable container, specialization for STL-like iterable container.	decItype(*(std::decIval<
iterable containers	210
qpp::is_matrix_expression< Derived >	
Checks whether the type is an Eigen matrix expression	211
qpp::QCircuit::iterator	
Quantum circuit bound-checking (safe) iterator	212
qpp::internal::KeyEqualEigen	
Functor for comparing Eigen expressions	217
qpp::make_void< Ts >	
Helper for qpp::to_void<> alias template	218
qpp::exception::MatrixMismatchSubsys	
Matrix mismatch subsystems exception	219
qpp::exception::MatrixNotCvector	
Matrix is not a column vector exception	221
qpp::exception::MatrixNotRvector	
Matrix is not a row vector exception	223
qpp::exception::MatrixNotSquare	
Matrix is not square exception	225
qpp::exception::MatrixNotSquareNorCvector	
Matrix is not square nor column vector exception	227
qpp::exception::MatrixNotSquareNorRvector	LLI
Matrix is not square nor row vector exception	220
qpp::exception::MatrixNotSquareNorVector	LLJ
Matrix is not square nor vector exception	221
qpp::exception::MatrixNotVector	201
Matrix is not a vector exception	233
qpp::QCircuit::MeasureStep	200
One step consisting only of measurements in the circuit	235
pp::exception::NoCodeword	200
Codeword does not exist exception	237
qpp::NoiseBase< T >	237
Base class for all noise models, derive your particular noise model	230
qpp::NoiseType	200
	246
Contains template tags used to specify the noise type	240
qpp::exception::NotBipartite	0.47
Not bi-partite exception	247
qpp::exception::NotImplemented	040
Code not yet implemented	249
qpp::exception::NotQubitCvector	051
Column vector is not 2 x 1 exception	201
qpp::exception::NotQubitMatrix	050
Matrix is not 2 x 2 exception	253

4.1 Class List

qpp::exception::NotQubitRvector	
Row vector is not 1 x 2 exception	255
qpp::exception::NotQubitSubsys Subsystems are not qubits exception	257
qpp::exception::NotQubitVector	231
Vector is not 2 x 1 nor 1 x 2 exception	259
qpp::exception::OutOfRange	
Argument out of range exception	261
qpp::exception::PermInvalid	
Invalid permutation exception	263
qpp::exception::PermMismatchDims	
Permutation mismatch dimensions exception	265
qpp::QCircuit	
Quantum circuit class	267
qpp::QEngine	
Quantum circuit engine, executes qpp::QCircuit	294
qpp::QubitAmplitudeDampingNoise	
Qubit amplitude damping noise, as described in Nielsen and Chuang	303
qpp::QubitBitFlipNoise	
Qubit bit flip noise	305
qpp::QubitBitPhaseFlipNoise	
Qubit bit-phase flip (dephasing) noise	306
qpp::QubitDepolarizingNoise	
Qubit depolarizing noise	308
qpp::QubitPhaseDampingNoise	000
Qubit phase damping noise, as described in Nielsen and Chuang	309
qpp::QubitPhaseFlipNoise	044
Qubit phase flip (dephasing) noise	311
Qudit was already measured exception	312
qpp::QuditDepolarizingNoise	312
Qudit depolarizing noise	314
qpp::RandomDevices	01-
Singleton class that manages the source of randomness in the library	317
qpp::internal::Singleton< T >	017
Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously	
recurring template pattern)	320
qpp::exception::SizeMismatch	
Size mismatch exception	323
qpp::NoiseType::StateDependent	
Template tag, used whenever the noise is state-dependent	325
qpp::NoiseType::StateIndependent	
Template tag, used whenever the noise is state-independent	325
qpp::States	
Const Singleton class that implements most commonly used states	325
qpp::exception::SubsysMismatchDims	
Subsystems mismatch dimensions exception	335
qpp::Timer< T, CLOCK_T >	
Chronometer	337
qpp::exception::TypeMismatch	
Type mismatch exception	342
qpp::exception::UndefinedType	
Not defined for this type exception	344
qpp::exception::Unknown	0.44
Unknown exception	346
qpp::QCircuit::iterator::value_type	348
qpp::exception::ZeroSize Object has zero size exception	352
Object has zero size exception	JJ2

10 Class Index

Chapter 5

File Index

5.1 File List

Here is a list of all files with brief descriptions:

constants.h	
Constants	365
entanglement.h	
Entanglement functions	366
entropies.h	
Entropy functions	368
functions.h	
Generic quantum computing functions	369
input_output.h	
Input/output functions	374
instruments.h	
Measurement functions	375
number_theory.h	
Number theory functions	381
operations.h	
Quantum operation functions	383
qpp.h	
Quantum++ main header file, includes all other necessary headers	385
random.h	
Randomness-related functions	387
statistics.h	
Statistics functions	388
traits.h	
Type traits	389
types.h	
Type aliases	391
classes/circuits.h	
Support for qudit quantum circuits	355
classes/codes.h	
Quantum error correcting codes	356
classes/exception.h	
Exceptions	357
classes/gates.h	
Quantum gates	359

12 File Index

classes/idisplay.h	
Display interface via the non-virtual interface (NVI) and very basic JSON serialization support	
interface	360
classes/init.h	
Initialization	360
classes/noise.h	
Noise models	361
classes/random_devices.h	
Random devices	362
classes/reversible.h	
Support for classical reversible circuits	363
classes/states.h	
Quantum states	363
classes/timer.h	
Timing	364
experimental/experimental.h	
Experimental/test functions/classes	369
internal/util.h	
Internal utility functions	378
internal/classes/iomanip.h	
Input/output manipulators	377
internal/classes/singleton.h	
Singleton pattern via CRTP	378
MATLAB/matlab.h	
Input/output interfacing with MATLAB	380

Chapter 6

Namespace Documentation

6.1 qpp Namespace Reference

Quantum++ main namespace.

Namespaces

· exception

Quantum++ exception hierarchy namespace.

· experimental

Experimental/test functions/classes, do not use or modify.

internal

Internal utility functions, do not use them directly or modify them.

literals

Classes

· class Bit_circuit

Classical reversible circuit simulator.

class Codes

const Singleton class that defines quantum error correcting codes

· class Dynamic_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

· class Gates

const Singleton class that implements most commonly used gates

class IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

class IJSON

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

class Init

const Singleton class that performs additional initializations/cleanups

· struct is complex

Checks whether the type is a complex type.

- struct is_complex< std::complex< T > >

Checks whether the type is a complex number type, specialization for complex types.

· struct is_iterable

Checks whether T is compatible with an STL-like iterable container.

 $\bullet \ \ struct \ is_iterable < T, \ to_void < \ decltype(std::declval < T > ().begin()), \ decltype(std::declval < T > ().end()), \ decltype(*(std::declval < T > ().end())), \ decltype(*(std::declval < T > ().end()))), \ decltype(*(std::declv$

Checks whether T is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

• struct is_matrix_expression

Checks whether the type is an Eigen matrix expression.

· struct make void

Helper for qpp::to_void<> alias template.

· class NoiseBase

Base class for all noise models, derive your particular noise model.

class NoiseType

Contains template tags used to specify the noise type.

class QCircuit

Quantum circuit class.

· class QEngine

Quantum circuit engine, executes qpp::QCircuit.

· class QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

class QubitBitFlipNoise

Qubit bit flip noise.

• class QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

· class QubitDepolarizingNoise

Qubit depolarizing noise.

· class QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

class QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

· class QuditDepolarizingNoise

Qudit depolarizing noise.

· class RandomDevices

Singleton class that manages the source of randomness in the library.

· class States

const Singleton class that implements most commonly used states

· class Timer

Chronometer.

Typedefs

```
• template<typename... Ts>
```

```
using to_void = typename make_void < Ts... >::type
```

Alias template that implements the proposal for void_t.

• using idx = std::size t

Non-negative integer index, make sure you use an unsigned type.

• using bigint = long long int

Big integer.

• using cplx = std::complex< double >

Complex number in double precision.

• using ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector. using bra = Eigen::RowVectorXcd Complex (double precision) dynamic Eigen row vector. • using cmat = Eigen::MatrixXcd Complex (double precision) dynamic Eigen matrix. using dmat = Eigen::MatrixXd Real (double precision) dynamic Eigen matrix. template<typename Scalar > using dyn mat = Eigen::Matrix < Scalar, Eigen::Dynamic, Eigen::Dynamic > Dynamic Eigen matrix over the field specified by Scalar. • template<typename Scalar > using dyn_col_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 > Dynamic Eigen column vector over the field specified by Scalar. template<typename Scalar > using dyn_row_vect = Eigen::Matrix < Scalar, 1, Eigen::Dynamic > Dynamic Eigen row vector over the field specified by Scalar. **Functions** • constexpr cplx operator"" _i (long double x) noexcept User-defined literal for complex $i = \sqrt{-1}$ (real overload) cplx omega (idx D) D-th root of unity. • template<typename Derived > dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt coefficients of the bi-partite pure state A. template<typename Derived > dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2) Schmidt coefficients of the bi-partite pure state A. template<typename Derived > cmat schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt basis on Alice side. • template<typename Derived > cmat schmidtA (const Eigen::MatrixBase< Derived > &A, idx d=2) Schmidt basis on Alice side. template<typename Derived > cmat schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt basis on Bob side. template<typename Derived > cmat schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2) Schmidt basis on Bob side. template<typename Derived > std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt probabilities of the bi-partite pure state A.

std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)

double entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)

template<typename Derived >

template<typename Derived >

Schmidt probabilities of the bi-partite pure state A.

Entanglement of the bi-partite pure state A.

```
• template<typename Derived >
  double entanglement (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Entanglement of the bi-partite pure state A.
template<typename Derived >
  double gconcurrence (const Eigen::MatrixBase< Derived > &A)
     G-concurrence of the bi-partite pure state A.
template<typename Derived >
  double negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Negativity of the bi-partite mixed state A.

    template < typename Derived >

  double negativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Negativity of the bi-partite mixed state A.

    template < typename Derived >

  double lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Logarithmic negativity of the bi-partite mixed state A.
• template<typename Derived >
  double lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Logarithmic negativity of the bi-partite mixed state A.
• template<typename Derived >
  double concurrence (const Eigen::MatrixBase< Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.
• template<typename Derived >
  double entropy (const Eigen::MatrixBase< Derived > &A)
      von-Neumann entropy of the density matrix A

    double entropy (const std::vector< double > &prob)

     Shannon entropy of the probability distribution prob.
template<typename Derived >
  double renyi (const Eigen::MatrixBase< Derived > &A, double alpha)
      Renyi- \alpha entropy of the density matrix A, for \alpha \geq 0.

    double renyi (const std::vector< double > &prob, double alpha)

     Renyi- \alpha entropy of the probability distribution prob, for \alpha > 0.

    template<typename Derived >

  double tsallis (const Eigen::MatrixBase< Derived > &A, double q)
      Tsallis- q entropy of the density matrix A, for q > 0.

    double tsallis (const std::vector< double > &prob, double q)

      Tsallis- q entropy of the probability distribution prob, for q > 0.
• template<typename Derived >
  double qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx > &subsysB, const std::vector< idx > &dims)
     Quantum mutual information between 2 subsystems of a composite system.

    template<typename Derived >

  double gmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx > &subsysB, idx d=2)
      Quantum mutual information between 2 subsystems of a composite system.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > transpose (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > adjoint (const Eigen::MatrixBase< Derived > &A)
     Adjoint.
```

```
    template<typename Derived >

  dyn_mat< typename Derived::Scalar > inverse (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  Derived::Scalar trace (const Eigen::MatrixBase< Derived > &A)
      Trace
• template<typename Derived >
  Derived::Scalar det (const Eigen::MatrixBase< Derived > &A)
     Determinant.

    template<typename Derived >

  Derived::Scalar logdet (const Eigen::MatrixBase< Derived > &A)
     Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar sum (const Eigen::MatrixBase< Derived > &A)
      Element-wise sum of A.
• template<typename Derived >
  Derived::Scalar prod (const Eigen::MatrixBase< Derived > &A)
     Element-wise product of A.

    template<typename Derived >

  double norm (const Eigen::MatrixBase< Derived > &A)
     Frobenius norm.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > normalize (const Eigen::MatrixBase< Derived > &A)
     Normalizes state vector (column or row vector) or density matrix.

    template<typename Derived >

  std::pair < dyn_col_vect < cplx >, cmat > eig (const Eigen::MatrixBase < Derived > &A)
     Full eigen decomposition.

    template<typename Derived >

  dyn_col_vect< cplx > evals (const Eigen::MatrixBase< Derived > &A)
     Eigenvalues.

    template<typename Derived >

  cmat evects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors.

    template<typename Derived >

  std::pair< dyn_col_vect< double >, cmat > heig (const Eigen::MatrixBase< Derived > &A)
     Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > hevals (const Eigen::MatrixBase< Derived > &A)
     Hermitian eigenvalues.
• template<typename Derived >
  cmat hevects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors of Hermitian matrix.
• template<typename Derived >
  std::tuple< cmat, dyn_col_vect< double >, cmat > svd (const Eigen::MatrixBase< Derived > &A)
     Full singular value decomposition.

    template<typename Derived >

  dyn_col_vect< double > svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.
• template<typename Derived >
  cmat svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.

    template<typename Derived >

  cmat svdV (const Eigen::MatrixBase< Derived > &A)
```

Direct sum.

```
Right singular vectors.
• template<typename Derived >
  cmat funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)

    template<typename Derived >

  cmat sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.

    template<typename Derived >

  cmat absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.

    template<typename Derived >

  cmat expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.

    template<typename Derived >

  cmat logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.
• template<typename Derived >
  cmat sinm (const Eigen::MatrixBase< Derived > &A)
     Matrix sin.

    template<typename Derived >

  cmat cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.
template<typename Derived >
  cmat spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.
• template<typename Derived >
  \label{eq:const_equation} \mbox{dyn\_mat} < \mbox{typename Derived::Scalar} > \mbox{powm (const Eigen::MatrixBase} < \mbox{Derived} > \&\mbox{A, idx n)}
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.
• template<typename Derived >
  double schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const type-
  name Derived::Scalar &))
     Functor.
• template<typename T >
  dyn_mat< typename T::Scalar > kron (const T &head)
     Kronecker product.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > kron (const T &head, const Args &... tail)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > kron (const std::vector< Derived > &As)
     Kronecker product.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > kron (const std::initializer_list< Derived > &As)
     Kronecker product.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Kronecker power.

    template<typename T >

  dyn_mat< typename T::Scalar > dirsum (const T &head)
```

```
• template<typename T, typename... Args>
  dyn_mat< typename T::Scalar > dirsum (const T &head, const Args &... tail)
     Direct sum.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > dirsum (const std::vector< Derived > &As)

    template<typename Derived >

  dyn mat< typename Derived::Scalar > dirsum (const std::initializer list< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > reshape (const Eigen::MatrixBase< Derived > &A, idx rows, idx
  cols)
     Reshape.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > comm (const Eigen::MatrixBase< Derived1 > &A, const Eigen::⊷
  MatrixBase< Derived2 > &B)
     Commutator.

    template<typename Derived1, typename Derived2 >

  dyn_mat< typename Derived1::Scalar > anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > prj (const Eigen::MatrixBase< Derived > &A)
     Projector.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > grams (const std::vector< Derived > &As)
     Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > grams (const std::initializer_list< Derived > &As)
      Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > grams (const Eigen::MatrixBase< Derived > &A)
     Gram-Schmidt orthogonalization.

    std::vector< idx > n2multiidx (idx n, const std::vector< idx > &dims)

     Non-negative integer index to multi-index.

    idx multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

     Multi-index to non-negative integer index.

    ket mket (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Multi-partite qudit ket.

    ket mket (const std::vector< idx > &mask, idx d=2)

     Multi-partite qudit ket.

    cmat mprj (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Projector onto multi-partite qudit ket.

    cmat mprj (const std::vector < idx > &mask, idx d=2)

     Projector onto multi-partite qudit ket.
• template<typename InputIterator >
  std::vector< double > abssq (InputIterator first, InputIterator last)
```

Computes the absolute values squared of an STL-like range of complex numbers.

• template<typename Container >

std::vector< double > abssq (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Computes the absolute values squared of an STL-like container.

template<typename Derived >

```
std::vector< double > abssq (const Eigen::MatrixBase< Derived > &A)
```

Computes the absolute values squared of an Eigen expression.

template<typename InputIterator >

std::iterator_traits< InputIterator >::value_type sum (InputIterator first, InputIterator last)

Element-wise sum of an STL-like range.

• template<typename Container >

Container::value_type sum (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

std::iterator traits< InputIterator >::value type prod (InputIterator first, InputIterator last)

Element-wise product of an STL-like range.

• template<typename Container >

Container::value_type prod (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Element-wise product of the elements of an STL-like container.

template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > rho2pure (const Eigen::MatrixBase< Derived > &A)
```

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

std::vector< idx > complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

• template<typename Derived >

```
std::vector< double > rho2bloch (const Eigen::MatrixBase< Derived > &A)
```

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

• template<typename Derived >

```
std::size_t hash_eigen_expression (const Eigen::MatrixBase< Derived > &A)
```

Computes the hash of en Eigen matrix/vector/expression.

 $\bullet \ \ \mathsf{template} \mathord{<} \mathsf{typename} \ \mathsf{Derived} >$

internal::IOManipEigen disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)

Eigen expression ostream manipulator.

internal::IOManipEigen disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

• template<typename InputIterator >

internal::IOManipRange < InputIterator > disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")

Range ostream manipulator.

• template<typename Container >

internal::IOManipRange< typename Container::const_iterator > disp (const Container &c, const std::string &separator, const std::string &start="[", const std::string &end="]", typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

template<typename PointerType >

 $\label{localizero} \begin{array}{l} \textbf{internal::IOManipPointer} < \textbf{PointerType} > \textbf{disp} \ (\textbf{const PointerType *p, idx N, const std::string \&separator, const std::string \&start="[", const std::string &end="]")} \end{array}$

C-style pointer ostream manipulator.

template<typename Derived >

void save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

ullet template<typename Derived >

dyn_mat< typename Derived::Scalar > load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)

Generalized inner product.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

template<typename Derived >

std::tuple < idx, std::vector < double >, std::vector < cmat > > measure (const Eigen::MatrixBase < Derived > &A, const std::vector < cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple < idx, std::vector < double >, std::vector < cmat > > measure (const Eigen::MatrixBase < Derived > &A, const std::initializer_list < cmat > &Ks, const std::vector < idx > &target, const std::vector < idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

```
std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)
```

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

```
std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)
```

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

```
std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector< idx > &dims)
```

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

```
std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)
```

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

```
std::tuple < std::vector < idx >, double, cmat > measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)
```

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

• template<typename Derived >

std::tuple< std::vector< idx >, double, cmat > measure_seq (const Eigen::MatrixBase< Derived > &A, std::vector< idx > target, idx d=2)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< cplx > >::type loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::← Scalar > >::type loadMATLAB (const std::string &mat file, const std::string &var name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

std::vector< int > x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

• bigint gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > invperm (const std::vector< idx > &perm)

Inverse permutation.

std::vector< idx > compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

std::vector< bigint > factors (bigint a)

Prime factor decomposition.

• bigint modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

bigint modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple < bigint, bigint, bigint > egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint modinv (bigint a, bigint p)

Modular inverse of a mod p.

bool isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

• bigint randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

std::vector< std::pair< int, int > > convergents (const std::vector< int > &cf)
 Convergents.

std::vector< std::pair< int, int > > convergents (double x, idx N)

Convergents.

template<typename Derived1 , typename Derived2 >

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, idx
d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)
```

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, const std::vector< idx > &dims)
```

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

 $\bullet \ \ \mathsf{template}{<}\mathsf{typename} \ \mathsf{Derived}>$

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, idx d=2)
```

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat kraus2super (const std::vector < cmat > &Ks)

Superoperator matrix.

cmat kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

• std::vector < cmat > choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

template<typename Derived >

```
dyn_mat< typename Derived::Scalar > ptrace1 (const Eigen::MatrixBase< Derived > &A, const std \leftarrow ::vector< idx > &dims)
```

Partial trace.

• template<typename Derived >

```
\label{eq:const_equal} \begin{tabular}{ll} $\tt dyn\_mat< typename\ Derived::Scalar > ptrace1\ (const\ Eigen::MatrixBase< Derived > \&A,\ idx\ d=2) \end{tabular}
```

Partial trace.

template<typename Derived >

```
dyn_mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)
```

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector<
idx > &target, const std::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector
idx > &target, idx d=2)

Partial trace.

template<typename Derived >

Partial transpose.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptranspose (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial transpose.

template<typename Derived >

 $\frac{dyn_mat}{<} typename \ Derived::Scalar > syspermute \ (const \ Eigen::MatrixBase < Derived > \&A, \ const \ std \\ \because vector < idx > \&perm, \ const \ std::vector < idx > \&dims)$

Subsystem permutation.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > syspermute (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &perm, idx d=2)

Subsystem permutation.

• template<typename Derived >

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_mat< typename Derived::Scalar > applyTFQ (const Eigen::MatrixBase< Derived > &A, const std↔ ::vector< idx > &target, idx d=2, bool swap=true)

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Qudit quantum Fourier transform.

• double rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

• bigint rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

• idx randidx (idx a=std::numeric_limits < idx >::min(), idx b=std::numeric_limits < idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

• template<typename Derived >

Derived rand (idx rows, idx cols, double a=0, double b=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

template<>

dmat rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

template<>

cmat rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived randn (idx rows, idx cols, double mean=0, double sigma=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

dmat randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

• template<>

cmat randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

• double randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

cmat randU (idx D=2)

Generates a random unitary matrix.

cmat randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector < cmat > randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat randH (idx D=2)

Generates a random Hermitian matrix.

ket randket (idx D=2)

Generates a random normalized ket (pure state vector)

• cmat randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.

std::vector< double > uniform (idx N)

Uniform probability distribution vector.

std::vector< double > marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > marginalY (const dmat &probXY)

Marginal distribution.

• template<typename Container >

double avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Average.

• template<typename Container >

double cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Covariance.

template<typename Container >
 double var (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable
 Container >::value >::type *=nullptr)

Variance.

• template<typename Container >

double sigma (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Standard deviation.

• template<typename Container >

double cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Correlation.

Variables

• constexpr double chop = 1e-10

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

• constexpr idx maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

• constexpr double pi = 3.141592653589793238462643383279502884

 π

• constexpr double ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

• constexpr double infty = std::numeric_limits<double>::max()

Used to denote infinity in double precision.

6.1.1 Detailed Description

Quantum++ main namespace.

6.1.2 Typedef Documentation

6.1.2.1 bigint

```
using qpp::bigint = typedef long long int
```

Big integer.

6.1.2.2 bra

```
using qpp::bra = typedef Eigen::RowVectorXcd
```

Complex (double precision) dynamic Eigen row vector.

```
6.1.2.3 cmat
```

```
using qpp::cmat = typedef Eigen::MatrixXcd
```

Complex (double precision) dynamic Eigen matrix.

6.1.2.4 cplx

```
using qpp::cplx = typedef std::complex<double>
```

Complex number in double precision.

6.1.2.5 dmat

```
using qpp::dmat = typedef Eigen::MatrixXd
```

Real (double precision) dynamic Eigen matrix.

6.1.2.6 dyn_col_vect

```
template<typename Scalar >
using qpp::dyn_col_vect = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, 1>
```

Dynamic Eigen column vector over the field specified by Scalar.

Example:

```
// type of colvect is Eigen::Matrix<float, Eigen::Dynamic, 1>
dyn_col_vect<float> colvect(2);
```

6.1.2.7 dyn_mat

```
template<typename Scalar >
using qpp::dyn_mat = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, Eigen::Dynamic>
```

Dynamic Eigen matrix over the field specified by Scalar.

Example:

```
// type of mat is Eigen::Matrix<float, Eigen::Dynamic, Eigen::Dynamic>
dyn_mat<float> mat(2, 3);
```

```
6.1.2.8 dyn_row_vect
```

```
template<typename Scalar >
using qpp::dyn_row_vect = typedef Eigen::Matrix<Scalar, 1, Eigen::Dynamic>
```

Dynamic Eigen row vector over the field specified by Scalar.

Example:

```
// type of rowvect is Eigen::Matrix<float, 1, Eigen::Dynamic>
dyn_row_vect<float> rowvect(3);
```

6.1.2.9 idx

```
using qpp::idx = typedef std::size_t
```

Non-negative integer index, make sure you use an unsigned type.

6.1.2.10 ket

```
using qpp::ket = typedef Eigen::VectorXcd
```

Complex (double precision) dynamic Eigen column vector.

6.1.2.11 to_void

```
template<typename... Ts>
using qpp::to_void = typedef typename make_void<Ts...>::type
```

Alias template that implements the proposal for void_t.

See also

```
http://www.open-std.org/jtc1/sc22/wg21/docs/papers/2014/n3911
```

6.1.3 Function Documentation

6.1.3.1 absm()

Matrix absolute value.

Parameters

```
A Eigen expression
```

Returns

Matrix absolute value of A

Computes the absolute values squared of an STL-like range of complex numbers.

Parameters

	Iterator to the first element of the range
last	Iterator to the last element of the range

InputIterator last)

Returns

Real vector consisting of the range absolute values squared

```
6.1.3.3 abssq() [2/3]
```

Computes the absolute values squared of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Real vector consisting of the container's absolute values squared

Computes the absolute values squared of an Eigen expression.

Parameters

```
A Eigen expression
```

Returns

Real vector consisting of the absolute values squared

6.1.3.5 adjoint()

Adjoint.

Parameters

```
A Eigen expression
```

Returns

Adjoint (Hermitian conjugate) of A, as a dynamic matrix over the same scalar field as A

6.1.3.6 anticomm()

Anti-commutator.

See also

qpp::comm()

Anti-commutator $\{A,B\} = AB + BA$. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
В	Eigen expression

Returns

Anti-commutator AB + BA, as a dynamic matrix over the same scalar field as A

6.1.3.7 apply() [1/5]

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

Returns

Gate A applied to the part target of state

6.1.3.8 apply() [2/5]

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

Returns

Gate A applied to the part target of state

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes where the Kraus operators Ks are applied
dims	Dimensions of the multi-partite system

Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes where the Kraus operators Ks are applied
d	Subsystem dimensions

Returns

Output density matrix after the action of the channel

6.1.3.12 applyCTRL() [1/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate *A* must match the dimension of *target*. Also, all control subsystems in *ctrl* must have the same dimension.

Parameters

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

Returns

CTRL-A gate applied to the part target of state

6.1.3.13 applyCTRL() [2/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

Returns

CTRL-A gate applied to the part target of state

6.1.3.14 applyQFT()

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

Parameters

Α	Eigen expression
target	Subsystem indexes where the QFT is applied
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Qudit Quantum Fourier transform applied to the part target of A

6.1.3.15 applyTFQ()

Applies the inverse (adjoint) qudit quantum Fourier transform to the part *target* of the multi-partite state vector or density matrix *A*.

Parameters

	Α	Eigen expression
	target	Subsystem indexes where the TFQ is applied
	d	Subsystem dimensions
ĺ	swap	Swaps the qubits/qudits at the end (true by default)

Returns

Inverse (adjoint) qudit Quantum Fourier transform applied to the part target of A

6.1.3.16 avg()

Average.

Parameters

prob	Real probability vector representing the probability distribution of X
Χ	Real random variable values represented by an STL-like container

Returns

Average of X

6.1.3.17 bloch2rho()

Computes the density matrix corresponding to the 3-dimensional real Bloch vector *r*.

See also

qpp::rho2bloch()

Parameters

r 3-dimensional real vector

Returns

Qubit density matrix

6.1.3.18 choi2kraus()

Orthogonal Kraus operators from Choi matrix.

See also

qpp::kraus2choi()

Extracts a set of orthogonal (under Hilbert-Schmidt operator norm) Kraus operators from the Choi matrix A

Note

The Kraus operators satisfy $Tr(K_i^{\dagger}K_j)=\delta_{ij}$ for all $i\neq j$

Parameters



Returns

Set of orthogonal Kraus operators


6.1.3.19 choi2super()

Converts Choi matrix to superoperator matrix.

See also

qpp::super2choi()

Parameters



Returns

Superoperator matrix

6.1.3.20 comm()

Commutator.

See also

qpp::anticomm()

Commutator [A, B] = AB - BA. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
В	Eigen expression

Returns

Commutator AB - BA, as a dynamic matrix over the same scalar field as A

6.1.3.21 complement()

Constructs the complement of a subsystem vector.

Parameters

subsys	Subsystem vector
n	Total number of systems

Returns

Complement of *subsys* with respect to the set $\{0, 1, \dots, n-1\}$

6.1.3.22 compperm()

Compose permutations.

Parameters

perm	Permutation
sigma	Permutation

Returns

Composition of the permutations *perm* o *sigma* = perm(sigma)

6.1.3.23 concurrence()

Wootters concurrence of the bi-partite qubit mixed state A.

Parameters

```
A Eigen expression
```

Returns

Wootters concurrence

6.1.3.24 conjugate()

Complex conjugate.

Parameters

```
A Eigen expression
```

Returns

Complex conjugate of A, as a dynamic matrix over the same scalar field as A

6.1.3.25 contfrac2x()

Real representation of a simple continued fraction.

See also

```
qpp::x2contfrac()
```

Note

If N is greater than the size of cf (by default it is), then all terms in cf are considered.

Parameters

	Integer vector containing the simple continued fraction expansion
Ν	Number of terms considered in the continued fraction expansion.

Returns

Real representation of the simple continued fraction

6.1.3.26 convergents() [1/2]

```
std::vector<std::pair<int, int> > qpp::convergents ( const std::vector< int > & cf ) [inline]
```

Convergents.

See also

```
qpp::contfrac2x() and qpp::x2contfrac()
```

Parameters

```
cf Continued fraction
```

Returns

Vector of convergents pairs (a_k, b_k) that approximate the number represented by the continued fraction

6.1.3.27 convergents() [2/2]

Convergents.

See also

```
qpp::contfrac2x() and qpp::x2contfrac()
```

Note

In the continued fraction expansion of x has less terms than N, then the series of convergents is truncated to the number of terms in the continued fraction expansion of x.

Parameters

Х	Real number
Ν	Number of convergents.

Returns

Vector of convergents pairs (a_k,b_k) that approximate the number \emph{x}

6.1.3.28 cor()

Correlation.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels the rows, Y labels the columns)
Χ	Real random variable values represented by an STL-like container
Υ	Real random variable values represented by an STL-like container

Returns

Correlation of X and Y

6.1.3.29 cosm()

Matrix cos.

Parameters

```
A Eigen expression
```

Returns

Matrix cosine of A

6.1.3.30 cov()

Covariance.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels the rows, Y labels the columns)
Χ	Real random variable values represented by an STL-like container
Y	Real random variable values represented by an STL-like container

Returns

Covariance of X and Y

6.1.3.31 cwise()

Functor.

Parameters

Α	Eigen expression
f	Pointer-to-function from scalars of A to OutputScalar

Returns

Component-wise f(A), as a dynamic matrix over the *OutputScalar* scalar field

6.1.3.32 det()

Determinant.

Parameters

A Eigen expression

Returns

Determinant of A, as a scalar over the same scalar field as A. Returns $\pm \infty$ when the determinant overflows/underflows.

```
6.1.3.33 dirsum() [1/4]
```

Direct sum.

See also

qpp::dirsumpow()

Used to stop the recursion for the variadic template version of qpp::dirsum()

head	Eigen expression
ncau	Ligon capicosion

Its argument head

Direct sum.

See also

qpp::dirsumpow()

Parameters

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

Returns

Direct sum of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

```
6.1.3.35 dirsum() [3/4]
```

Direct sum.

See also

qpp::dirsumpow()

Parameters

As std::vector of Eigen expressions

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Direct sum.

See also

qpp::dirsumpow()

Parameters

As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}

Returns

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.3.37 dirsumpow()

Direct sum power.

See also

qpp::dirsum()

Α	Eigen expression
n	Non-negative integer

Direct sum of A with itself n times $A^{\oplus n}$, as a dynamic matrix over the same scalar field as A

Eigen expression ostream manipulator.

Parameters

Α	Eigen expression
chop	Set to zero the elements smaller in absolute value than <i>chop</i>

Returns

Instance of qpp::internal::IOManipEigen

Complex number ostream manipulator.

Parameters

Z	Complex number (or any other type implicitly cast-able to std::complex <double>)</double>
chop	Set to zero the elements smaller in absolute value than chop

Returns

Instance of qpp::internal::IOManipEigen

```
6.1.3.40 disp() [3/5]

template<typename InputIterator >
internal::IOManipRange<InputIterator> qpp::disp (
```

```
InputIterator first,
InputIterator last,
const std::string & separator,
const std::string & start = "[",
const std::string & end = "]")
```

Range ostream manipulator.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipRange

```
6.1.3.41 disp() [4/5]
```

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

Parameters

С	Container
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipRange

6.1.3.42 disp() [5/5]

```
template<typename PointerType >
internal::IOManipPointer<PointerType> qpp::disp (
```

```
const PointerType * p,
idx N,
const std::string & separator,
const std::string & start = "[",
const std::string & end = "]")
```

C-style pointer ostream manipulator.

Parameters

р	Pointer to the first element
N	Number of elements to be displayed
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipPointer

6.1.3.43 egcd()

Extended greatest common divisor of two integers.

See also

qpp::gcd()

Parameters

а	Integer
b	Integer

Returns

Tuple of: 1. Integer m, 2. Integer n, and 3. Non-negative integer gcd(a,b) such that ma + nb = gcd(a,b)

6.1.3.44 eig()

Full eigen decomposition.

See also

qpp::heig()

Parameters

```
A Eigen expression
```

Returns

Pair of: 1. Eigenvalues of *A*, as a complex dynamic column vector, and 2. Eigenvectors of *A*, as columns of a complex dynamic matrix

6.1.3.45 entanglement() [1/2]

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

```
qpp::entropy()
```

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Entanglement, with the logarithm in base 2

6.1.3.46 entanglement() [2/2]

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

qpp::entropy()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Entanglement, with the logarithm in base 2

6.1.3.47 entropy() [1/2]

von-Neumann entropy of the density matrix A

Parameters

```
A Eigen expression
```

Returns

von-Neumann entropy, with the logarithm in base 2

6.1.3.48 entropy() [2/2]

Shannon entropy of the probability distribution prob.

Parameters

prob Real probability vector

Returns

Shannon entropy, with the logarithm in base 2

```
6.1.3.49 evals()
```

Eigenvalues.

See also

qpp::hevals()

Parameters

```
A Eigen expression
```

Returns

Eigenvalues of A, as a complex dynamic column vector

6.1.3.50 evects()

Eigenvectors.

See also

qpp::hevects()

Parameters

```
A Eigen expression
```

Returns

Eigenvectors of A, as columns of a complex dynamic matrix

6.1.3.51 expm()

Matrix exponential.

Parameters

A Eigen expression

Returns

Matrix exponential of A

6.1.3.52 factors()

Prime factor decomposition.

Note

Runs in $\mathcal{O}(\sqrt{n})$ time complexity

Parameters

a Integer different from 0, 1 or -1

Returns

Integer vector containing the factors

6.1.3.53 funm()

Functional calculus f(A)

Α	Eigen expression
f	Pointer-to-function from complex to complex

```
Returns
```

```
f(A)
```

Greatest common divisor of two integers.

See also

```
qpp::lcm()
```

Parameters

а	Integer
b	Integer

Returns

Greatest common divisor of a and b

Greatest common divisor of a list of integers.

See also

```
qpp::lcm()
```

Parameters

```
as List of integers
```

Returns

Greatest common divisor of all numbers in as

6.1.3.56 gconcurrence()

G-concurrence of the bi-partite pure state A.

Note


Both local dimensions must be equal

Uses qpp::logdet() to avoid overflows

See also

qpp::logdet()

Parameters



Returns

G-concurrence

```
6.1.3.57 grams() [1/3]
```

Gram-Schmidt orthogonalization.

Parameters

```
As std::vector of Eigen expressions as column vectors
```

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

```
6.1.3.58 grams() [2/3]
```

Gram-Schmidt orthogonalization.

Parameters

```
As std::initializer_list of Eigen expressions as column vectors
```

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

Gram-Schmidt orthogonalization.

Parameters

A | Eigen expression, the input vectors are the columns of A

Returns

Gram-Schmidt vectors of the columns of A, as columns of a dynamic matrix over the same scalar field as A

6.1.3.60 hash_eigen_expression()

Computes the hash of en Eigen matrix/vector/expression.

Note

```
Code taken from boost::hash_combine(), see https://www.boost.org/doc/libs/1_69_← 0/doc/html/hash/reference.html#boost.hash combine
```

Parameters

A Eigen expression

Hash of its argument

6.1.3.61 heig()

Full eigen decomposition of Hermitian expression.

See also

qpp::eig()

Parameters

A Eigen expression

Returns

Pair of: 1. Eigenvalues of A, as a real dynamic column vector, and 2. Eigenvectors of A, as columns of a complex dynamic matrix

6.1.3.62 hevals()

Hermitian eigenvalues.

See also

qpp::evals()

Parameters

A Eigen expression

Returns

Eigenvalues of Hermitian A, as a real dynamic column vector


6.1.3.63 hevects()

Eigenvectors of Hermitian matrix.

See also

qpp::evects()

Parameters



Returns

Eigenvectors of Hermitian matrix A, as columns of a complex matrix

6.1.3.64 inverse()

Inverse.

Parameters

```
A Eigen expression
```

Returns

Inverse of A, as a dynamic matrix over the same scalar field as A

6.1.3.65 invperm()

Inverse permutation.

Parameters

perm	Permutation

Returns

Inverse of the permutation perm

Generalized inner product.

Parameters

phi	Column vector Eigen expression	
psi	Column vector Eigen expression	
subsys	Subsystem indexes over which phi is defined	
dims	Dimensions of the multi-partite system	

Returns

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

```
6.1.3.67 ip() [2/2]
```

Generalized inner product.

phi	Column vector Eigen expression
psi	Column vector Eigen expression
subsys	Subsystem indexes over which phi is defined
Generated by	Subsystem dimensions

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

6.1.3.68 isprime()

Primality test based on the Miller-Rabin's algorithm.

Parameters

р	Integer different from 0, 1 or -1
k	Number of iterations. The probability of a false positive is 2^{-k} .

Returns

True if the number is (most-likely) prime, false otherwise

6.1.3.69 kraus2choi()

Choi matrix.

See also

qpp::choi2kraus()

Constructs the Choi matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|, |0\rangle\langle 1|$ etc.

Note

The superoperator matrix S and the Choi matrix C are related by $S_{ab,mn}=C_{ma,nb}$

|--|

Choi matrix

6.1.3.70 kraus2super()

Superoperator matrix.

Constructs the superoperator matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|$, $|0\rangle\langle 1|$ etc.

Parameters

```
Ks Set of Kraus operators
```

Returns

Superoperator matrix

```
6.1.3.71 kron() [1/4]
```

Kronecker product.

See also

qpp::kronpow()

Used to stop the recursion for the variadic template version of app::kron()

Parameters

```
head Eigen expression
```

Returns

Its argument head

```
6.1.3.72 kron() [2/4]
```

Kronecker product.

See also

qpp::kronpow()

Parameters

head Eigen expression	
tail	Variadic Eigen expression (zero or more parameters)

Returns

Kronecker product of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

```
6.1.3.73 kron() [3/4]
```

Kronecker product.

See also

qpp::kronpow()

Parameters

Δc	std::vector of Eigen expressions
713	sidvector or Ligeri expressions

Returns

Kronecker product of all elements in *As*, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Kronecker product.

See also

qpp::kronpow()

Parameters

As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}

Returns

Kronecker product of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.3.75 kronpow()

Kronecker power.

See also

qpp::kron()

Parameters

Α	Eigen expression
n	Non-negative integer

Returns

Kronecker product of A with itself n times $A^{\otimes n}$, as a dynamic matrix over the same scalar field as A

Least common multiple of two integers.

See also

qpp::gcd()

Parameters

а	Integer
b	Integer

Returns

Least common multiple of a and b

Least common multiple of a list of integers.

See also

qpp::gcd()

Parameters

```
as List of integers
```

Returns

Least common multiple of all numbers in as

6.1.3.78 load()

Loads Eigen matrix from a binary file (internal format) in double precision.

See also

qpp::save()

The template parameter cannot be automatically deduced and must be explicitly provided, depending on the scalar field of the matrix that is being loaded.

Example:

```
// loads a previously saved Eigen dynamic complex matrix from "input.bin"
cmat mat = load<cmat>("input.bin");
```

Parameters

fname	Output file name
mamo	Output mo name

6.1.3.79 loadMATLAB() [1/2]

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

qpp::saveMATLAB()

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen ket
// from the MATLAB file "input.mat"
ket psi = loadMATLABket>("input.mat");
```

Template Parameters

Derived	Complex Eigen type
---------	--------------------

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be loaded

Eigen dynamic matrix

```
6.1.3.80 loadMATLAB() [2/2]
```

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

```
qpp::saveMATLAB()
```

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen dynamic double matrix
// from the MATLAB file "input.mat"
dmat mat = loadMATLAB<dmat>("input.mat");
```

Template Parameters

Parameters

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be loaded

Returns

Eigen dynamic matrix

6.1.3.81 logdet()

Logarithm of the determinant.

Useful when the determinant overflows/underflows

Parameters

A Eigen expression

Returns

Logarithm of the determinant of A, as a scalar over the same scalar field as A

6.1.3.82 logm()

Matrix logarithm.

Parameters

```
A Eigen expression
```

Returns

Matrix logarithm of A

6.1.3.83 lognegativity() [1/2]

Logarithmic negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Logarithmic negativity, with the logarithm in base 2

6.1.3.84 lognegativity() [2/2]

Logarithmic negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Logarithmic negativity, with the logarithm in base 2

6.1.3.85 marginalX()

Marginal distribution.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels	1
	the rows, Ylabels the columns)	

Returns

Real vector consisting of the marginal distribution of X

6.1.3.86 marginalY()

Marginal distribution.

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels
	the rows, Y labels the columns)

Real vector consisting of the marginal distribution of Y

Measures the state vector or density operator A using the set of Kraus operators Ks.

const std::vector< cmat > & Ks)

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.88 measure() [2/9]

Measures the state vector or density matrix A using the set of Kraus operators Ks.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

Parameters

Α	Eigen expression
U	Unitary matrix whose columns represent the measurement basis vectors

const cmat & U)

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

const std::vector< idx > & target,
const std::vector< idx > & dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.92 measure() [6/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.93 measure() [7/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

ſ	Α	Eigen expression
	Ks	Set of Kraus operators
Ī	target	Subsystem indexes that are measured
Ī	d	Subsystem dimensions

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part *target* of the multi-partite state vector or density matrix *A* in the orthonormal basis or rank-1 projectors specified by the columns of the matrix *V*.

See also

```
qpp::measure_seq()
```

Note

The dimension of *V* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part *target* of the multi-partite state vector or density matrix *A* in the orthonormal basis or rank-1 projectors specified by the columns of the matrix *V*.

See also

```
qpp::measure_seq()
```

Note

The dimension of V must match the dimension of target. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression	
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors	
target	Subsystem indexes that are measured	
d	Subsystem dimensions	

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

See also

qpp::measure()

Parameters

Α	Eigen expression
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

See also

```
qpp::measure()
```

Parameters

Α	Eigen expression
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|\text{mask}\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

Multi-partite qudit state vector, as a complex dynamic column vector

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension *d. mask* is a std::vector of non-negative integers, and each element in *mask* has to be strictly smaller than *d*.

Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Multi-partite qudit state vector, as a complex dynamic column vector

6.1.3.100 modinv()

Modular inverse of a mod p.

See also

qpp::egcd()

Note

a and p must be co-prime

а	Non-negative integer
р	Non-negative integer

Returns

Modular inverse $a^{-1} \mod p$

6.1.3.101 modmul()

Modular multiplication without overflow.

Computes $ab \bmod p$ without overflow

Parameters

а	Integer
b	Integer
р	Positive integer

Returns

ab mod p avoiding overflow

6.1.3.102 modpow()

Fast integer power modulo *p* based on the SQUARE-AND-MULTIPLY algorithm.

Note

Uses qpp::modmul() that avoids overflows

Computes $a^n \mod p$

а	Non-negative integer
n	Non-negative integer
р	Strictly positive integer

Returns

```
a^n \bmod p
```

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

Parameters

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

6.1.3.105 multiidx2n()

```
idx qpp::multiidx2n ( const \ std::vector < \ idx > \& \ midx, const \ std::vector < \ idx > \& \ dims \ ) \quad [inline]
```

Multi-index to non-negative integer index.

See also

```
qpp::n2multiidx()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

Parameters

midx	Multi-index
dims	Dimensions of the multi-partite system

Returns

Non-negative integer index

6.1.3.106 n2multiidx()

Non-negative integer index to multi-index.

See also

```
qpp::multiidx2n()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

n	Non-negative integer index
dims	Dimensions of the multi-partite system

Returns

Multi-index of the same size as dims

```
6.1.3.107 negativity() [1/2]
```

Negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Negativity

```
6.1.3.108 negativity() [2/2]
```

```
template<typename Derived > double qpp::negativity ( const Eigen::MatrixBase< Derived > & A, idx d = 2)
```

Negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Negativity

6.1.3.109 norm()

Frobenius norm.

Parameters

A Eigen expression

Returns

Frobenius norm of A

6.1.3.110 normalize()

Normalizes state vector (column or row vector) or density matrix.

Parameters

A Eigen expression

Returns

Normalized state vector or density matrix

6.1.3.111 omega()

```
cplx qpp::omega (
        idx D ) [inline]
```

D-th root of unity.

Parameters

D Non-negative integer

D-th root of unity $\exp(2\pi i/D)$

6.1.3.113 powm()

Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

See also

qpp::spectralpowm()

Explicitly multiplies the matrix A with itself n times. By convention $A^0 = I$.

Parameters

Α	Eigen expression
n	Non-negative integer

Returns

Matrix power A^n , as a dynamic matrix over the same scalar field as A

6.1.3.114 prj()

Projector.

Normalized projector onto state vector

Parameters

```
A Eigen expression
```

Returns

Projector onto the state vector A, or the matrix Zero if A has norm zero, as a dynamic matrix over the same scalar field as A

6.1.3.115 prod() [1/3]

Element-wise product of A.

Parameters

```
A Eigen expression
```

Returns

Element-wise product of A, as a scalar over the same scalar field as A

6.1.3.116 prod() [2/3]

Element-wise product of an STL-like range.

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Element-wise product of the range, as a scalar over the same scalar field as the range

Element-wise product of the elements of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Element-wise product of the elements of the container, as a scalar over the same scalar field as the container

Partial trace.

See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Partial trace $Tr_{subsys}(\cdot)$ over the subsystems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

Partial trace.

See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial trace $Tr_{subsys}(\cdot)$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

```
6.1.3.120 ptrace1() [1/2]
```

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_A(\cdot)$ over the first subsytem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

```
6.1.3.121 ptrace1() [2/2]
```

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_A(\cdot)$ over the first subsystem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.122 ptrace2() [1/2]

Partial trace.

See also

```
qpp::ptrace1()
```

Partial trace over the second subsystem of bi-partite state vector or density matrix

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_B(\cdot)$ over the second subsytem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.123 ptrace2() [2/2]

Partial trace.

See also

qpp::ptrace1()

Partial trace over the second subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_B(\cdot)$ over the second subsytem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.124 ptranspose() [1/2]

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.3.125 ptranspose() [2/2]

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.3.126 QFT()

Qudit quantum Fourier transform.

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Qudit quantum Fourier transform applied on A

6.1.3.127 qmutualinfo() [1/2]

Quantum mutual information between 2 subsystems of a composite system.

Parameters

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
dims	Dimensions of the multi-partite system

Returns

Mutual information between the 2 subsystems

6.1.3.128 qmutualinfo() [2/2]

Quantum mutual information between 2 subsystems of a composite system.

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
d	Subsystem dimensions

Returns

Mutual information between the 2 subsystems

Generates a random real number uniformly distributed in the interval [a, b)

Parameters

а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Returns

Random real number (double) uniformly distributed in the interval [a, b)

Generates a random big integer uniformly distributed in the interval [a, b].

Note

To avoid ambiguity with double qpp::rand(double, double) cast at least one of the arguments to qpp::bigint

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

Random big integer uniformly distributed in the interval [a, b]

Generates a random matrix with entries uniformly distributed in the interval [a, b)

If complex, then both real and imaginary parts are uniformly distributed in [a, b)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries uniformly distributed in [-1,1)
dmat mat = rand<dmat>(3, 3, -1, 1);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd,
// with entries (both real and imaginary) uniformly distributed in [-1,1)
cmat mat = rand<cmat>(3, 3, -1, 1);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Returns

Random complex matrix

6.1.3.134 randH()

```
cmat qpp::randH (
    idx D = 2) [inline]
```

Generates a random Hermitian matrix.

Parameters

D Dimension of the Hilbert space

Random Hermitian matrix

6.1.3.135 randidx()

```
idx qpp::randidx (
        idx a = std::numeric_limits<idx>::min(),
        idx b = std::numeric_limits<idx>::max() ) [inline]
```

Generates a random index (idx) uniformly distributed in the interval [a, b].

Parameters

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

Returns

Random index (idx) uniformly distributed in the interval [a, b]

6.1.3.136 randket()

```
ket qpp::randket (
idx D = 2) [inline]
```

Generates a random normalized ket (pure state vector)

Parameters

D Dimension of the Hilbert space

Returns

Random normalized ket

6.1.3.137 randkraus()

```
std::vector<cmat> qpp::randkraus (
    idx N,
    idx D = 2 ) [inline]
```

Generates a set of random Kraus operators.

Note

The set of Kraus operators satisfy the closure condition $\sum_i K_i^\dagger K_i = I$

Parameters

Ν	Number of Kraus operators
D	Dimension of the Hilbert space

Returns

Set of N Kraus operators satisfying the closure condition

Generates a random matrix with entries normally distributed in N(mean, sigma)

If complex, then both real and imaginary parts are normally distributed in N(mean, sigma)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries normally distributed in N(0,2)
dmat mat = randn<dmat>(3, 3, 0, 2);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Returns

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd, 
// with entries (both real and imaginary) normally distributed in N(0,2) cmat mat = randn<cmat>(3, 3, 0, 2);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Returns

Random complex matrix

Generates a random real number (double) normally distributed in N(mean, sigma)

Parameters

mean	Mean
sigma	Standard deviation

Returns

Random real number normally distributed in N(mean, sigma)

6.1.3.142 randperm()

```
std::vector<idx> qpp::randperm (
    idx N ) [inline]
```

Generates a random uniformly distributed permutation.

Uses Knuth shuffle method (as implemented by std::shuffle), so that all permutations are equally probable

Parameters

```
N Size of the permutation
```

Returns

Random permutation of size N

6.1.3.143 randprime()

```
bigint qpp::randprime (
          bigint a,
          bigint b,
          idx N = 1000 ) [inline]
```

Generates a random big prime uniformly distributed in the interval [a, b].

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it
N	Maximum number of candidates

Random big integer uniformly distributed in the interval [a, b]

6.1.3.144 randprob()

```
\label{eq:continuous_double} $$ $td::vector<double> qpp::randprob ( $$ idx N$) [inline]
```

Generates a random probability vector uniformly distributed over the probability simplex.

Parameters

N Size of the probability vector

Returns

Random probability vector

6.1.3.145 randrho()

```
cmat qpp::randrho (
    idx D = 2) [inline]
```

Generates a random density matrix.

Parameters

D Dimension of the Hilbert space

Returns

Random density matrix

6.1.3.146 randU()

```
cmat qpp::randU (
    idx D = 2) [inline]
```

Generates a random unitary matrix.

D Dimension of the Hilbert space

Returns

Random unitary

6.1.3.147 randV()

Generates a random isometry matrix.

Parameters

Din	Size of the input Hilbert space
Dout	Size of the output Hilbert space

Returns

Random isometry matrix

```
6.1.3.148 renyi() [1/2]
```

Renyi- α entropy of the density matrix A, for $\alpha \geq 0.$

Note

When $\alpha \to 1$ the Renyi entropy converges to the von-Neumann entropy, with the logarithm in base 2

Α	Eigen expression
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

Renyi- α entropy, with the logarithm in base 2

Renyi- α entropy of the probability distribution *prob*, for $\alpha \geq 0$.

Note

When $\alpha \to 1$ the Renyi entropy converges to the Shannon entropy, with the logarithm in base 2

Parameters

prob	Real probability vector
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

Returns

Renyi- α entropy, with the logarithm in base 2

6.1.3.150 reshape()

Reshape.

Uses column-major order when reshaping (same as MATLAB)

Α	Eigen expression
rows	Number of rows of the reshaped matrix
cols	Number of columns of the reshaped matrix

Reshaped matrix with rows rows and cols columns, as a dynamic matrix over the same scalar field as A

6.1.3.151 rho2bloch()

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

See also

qpp::bloch2rho()

Note

It is implicitly assumed that the density matrix is Hermitian

Parameters

```
A Eigen expression
```

Returns

3-dimensional Bloch vector

6.1.3.152 rho2pure()

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

Note

No purity check is done, the input state A must have rank one, otherwise the function returns the first non-zero eigenvector of A

Parameters

A Eigen expression, assumed to be proportional to a projector onto a pure state, i.e. A is assumed to have rank one

The unique non-zero eigenvector of A (up to a phase), as a dynamic column vector over the same scalar field as A

6.1.3.153 save()

Saves Eigen expression to a binary file (internal format) in double precision.

See also

qpp::load()

Parameters

Α	Eigen expression
fname	Output file name

6.1.3.154 saveMATLAB() [1/2]

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

qpp::loadMATLAB()

Template Parameters

Complex Eigen type

Α	Eigen expression over the complex field
---	---

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be saved
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details

6.1.3.155 saveMATLAB() [2/2]

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

qpp::loadMATLAB()

Template Parameters

igen type

Parameters

Α	Non-complex Eigen expression
mat_file	MATALB .mat file
var_name Variable name in the .mat file representing the matrix to be saved	
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details

6.1.3.156 schatten()

Schatten matrix norm.

	Α	Eigen expression
ſ	р	Real number, greater or equal to 1, use qpp::infty for $p = \infty$

Schatten-p matrix norm of A

Schmidt basis on Alice side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix \boldsymbol{U} whose columns represent the Schmidt basis vectors on Alice side.

Schmidt basis on Alice side.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix U whose columns represent the Schmidt basis vectors on Alice side.

6.1.3.159 schmidtB() [1/2] template<typename Derived > cmat qpp::schmidtB (

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & dims )
```

Schmidt basis on Bob side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

Schmidt basis on Bob side.

idx d = 2)

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.162 schmidtcoeffs() [2/2]

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.163 schmidtprobs() [1/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.3.164 schmidtprobs() [2/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.3.165 sigma()

Standard deviation.

prob	Real probability vector representing the probability distribution of X
X	Real random variable values represented by an STL-like container

Returns

Standard deviation of X

6.1.3.166 sinm()

Matrix sin.

Parameters

A Eigen expression

Returns

Matrix sine of A

6.1.3.167 spectralpowm()

Matrix power.

See also

qpp::powm()

Uses the spectral decomposition of \emph{A} to compute the matrix power. By convention $\emph{A}^0 = \emph{I}$.

Α	Eigen expression
Z	Complex number

Matrix power A^z

6.1.3.168 sqrtm()

Matrix square root.

Parameters

```
A Eigen expression
```

Returns

Matrix square root of A

```
6.1.3.169 sum() [1/3]
```

Element-wise sum of A.

Parameters

```
A Eigen expression
```

Returns

Element-wise sum of A, as a scalar over the same scalar field as A

```
6.1.3.170 sum() [2/3]
```

Element-wise sum of an STL-like range.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Element-wise sum of the range, as a scalar over the same scalar field as the range

Element-wise sum of the elements of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Element-wise sum of the elements of the container, as a scalar over the same scalar field as the container

6.1.3.172 super2choi()

Converts superoperator matrix to Choi matrix.

See also

qpp::choi2super()

Parameters

A Superoperator matrix

Returns

Choi matrix

6.1.3.173 svals()

Singular values.

Parameters

A Eigen expression

Returns

Singular values of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.174 svd()

Full singular value decomposition.

Parameters

A Eigen expression

Returns

Tuple of: 1. Left sigular vectors of A, as columns of a complex dynamic matrix, 2. Singular values of A, ordered in decreasing order, as a real dynamic column vector, and 3. Right singular vectors of A, as columns of a complex dynamic matrix

6.1.3.175 svdU()

Left singular vectors.

Parameters

```
A Eigen expression
```

Returns

Complex dynamic matrix, whose columns are the left singular vectors of A

6.1.3.176 svdV()

Right singular vectors.

Parameters

```
A Eigen expression
```

Returns

Complex dynamic matrix, whose columns are the right singular vectors of A

6.1.3.177 syspermute() [1/2]

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Parameters

Α	Eigen expression
perm	Permutation
dims	Dimensions of the multi-partite system

Returns

Permuted system, as a dynamic matrix over the same scalar field as A

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Parameters

Α	Eigen expression
perm	Permutation
d	Subsystem dimensions

Returns

Permuted system, as a dynamic matrix over the same scalar field as A

6.1.3.179 TFQ()

Inverse (adjoint) qudit quantum Fourier transform.

Parameters

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Inverse (adjoint) qudit quantum Fourier transform applied on A

6.1.3.180 trace()

Trace.

Parameters

```
A Eigen expression
```

Returns

Trace of A, as a scalar over the same scalar field as A

6.1.3.181 transpose()

Transpose.

Parameters

```
A Eigen expression
```

Returns

Transpose of A, as a dynamic matrix over the same scalar field as A

```
6.1.3.182 tsallis() [1/2] template<typename Derived > double qpp::tsallis ( const Eigen::MatrixBase< Derived > & A, double q)
```

Tsallis- q entropy of the density matrix A, for $q \ge 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the von-Neumann entropy, with the logarithm in base e

Parameters

Α	Eigen expression	
q	Non-negative real number	

Returns

Tsallis- q entropy

Tsallis- q entropy of the probability distribution *prob*, for $q \ge 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the Shannon entropy, with the logarithm in base e

Parameters

prob	Real probability vector
q	Non-negative real number

Returns

Tsallis- q entropy

6.1.3.184 uniform()

```
std::vector<double> qpp::uniform (
    idx N ) [inline]
```

Uniform probability distribution vector.

Parameters

N Size of the alphabet

Returns

Real vector consisting of a uniform distribution of size N

6.1.3.185 var()

Variance.

Parameters

prob	Real probability vector representing the probability distribution of X
Χ	Real random variable values represented by an STL-like container

Returns

Variance of X

6.1.3.186 x2contfrac()

Simple continued fraction expansion.

See also

```
qpp::contfrac2x()
```

Parameters

Х	Real number
Ν	Maximum number of terms in the expansion
cut	Stop the expansion when the next term is greater than cut

Returns

Integer vector containing the simple continued fraction expansion of x. If there are M less than N terms in the expansion, a shorter vector with M components is returned.

6.1.4 Variable Documentation

6.1.4.1 chop

```
constexpr double qpp::chop = 1e-10
```

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

6.1.4.2 ee

```
constexpr double qpp::ee = 2.718281828459045235360287471352662497
```

Base of natural logarithm, e.

6.1.4.3 infty

```
constexpr double qpp::infty = std::numeric_limits<double>::max()
```

Used to denote infinity in double precision.

6.1.4.4 maxn

```
constexpr idx qpp::maxn = 64
```

Maximum number of allowed qubits/qudits (subsystems)

Used internally to allocate arrays on the stack (for performance reasons):

6.1.4.5 pi

```
constexpr double qpp::pi = 3.141592653589793238462643383279502884 \pi
```

6.2 qpp::exception Namespace Reference

Quantum++ exception hierarchy namespace.

Classes

class CustomException

Custom exception.

· class DimsInvalid

Invalid dimension(s) exception.

· class DimsMismatchCvector

Dimension(s) mismatch column vector size exception.

· class DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

· class DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

· class DimsMismatchVector

Dimension(s) mismatch vector size exception.

· class DimsNotEqual

Dimensions not equal exception.

class Duplicates

System (e.g. std::vector) has duplicates exception.

class Exception

Base class for generating Quantum++ custom exceptions.

· class InvalidIterator

Invalid iterator.

class MatrixMismatchSubsys

Matrix mismatch subsystems exception.

class MatrixNotCvector

Matrix is not a column vector exception.

class MatrixNotRvector

Matrix is not a row vector exception.

class MatrixNotSquare

Matrix is not square exception.

class MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

class MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

class MatrixNotSquareNorVector

Matrix is not square nor vector exception.

class MatrixNotVector

Matrix is not a vector exception.

class NoCodeword

Codeword does not exist exception.

· class NotBipartite

Not bi-partite exception.

class NotImplemented

Code not yet implemented.

class NotQubitCvector

Column vector is not 2 x 1 exception.

class NotQubitMatrix

Matrix is not 2 x 2 exception.

class NotQubitRvector

Row vector is not 1 x 2 exception.

class NotQubitSubsys

Subsystems are not qubits exception.

· class NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

class OutOfRange

Argument out of range exception.

class PermInvalid

Invalid permutation exception.

class PermMismatchDims

Permutation mismatch dimensions exception.

· class QuditAlreadyMeasured

Qudit was already measured exception.

· class SizeMismatch

Size mismatch exception.

· class SubsysMismatchDims

Subsystems mismatch dimensions exception.

class TypeMismatch

Type mismatch exception.

class UndefinedType

Not defined for this type exception.

· class Unknown

Unknown exception.

· class ZeroSize

Object has zero size exception.

6.2.1 Detailed Description

Quantum++ exception hierarchy namespace.

6.3 qpp::experimental Namespace Reference

Experimental/test functions/classes, do not use or modify.

6.3.1 Detailed Description

Experimental/test functions/classes, do not use or modify.

6.4 qpp::internal Namespace Reference

Internal utility functions, do not use them directly or modify them.

Classes

- struct Display_Impl_
- · class HashEigen

Functor for hashing Eigen expressions.

- class IOManipEigen
- · class IOManipPointer
- · class IOManipRange
- · class KeyEqualEigen

Functor for comparing Eigen expressions.

class Singleton

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Functions

- template < class T >
 void hash combine (std::size t &seed, const T &v)
- void n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- template<typename Derived >

bool check square mat (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool check vector (const Eigen::MatrixBase< Derived > &A)

ullet template<typename Derived >

bool check_rvector (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

bool check_cvector (const Eigen::MatrixBase< Derived > &A)

• template<typename T >

bool check_nonzero_size (const T &x) noexcept

• template<typename T1 , typename T2 >

bool check_matching_sizes (const T1 &lhs, const T2 &rhs) noexcept

- bool check_dims (const std::vector < idx > &dims)
- $\bullet \ \ \mathsf{template} \mathord{<} \mathsf{typename} \ \mathsf{Derived} >$

bool check_dims_match_mat (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

 $\bullet \;\; {\sf template}{<} {\sf typename \; Derived} >$

bool check_dims_match_cvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ \text{template}{<} \text{typename Derived}>$

bool check_dims_match_rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- bool check_eq_dims (const std::vector< idx > &dims, idx dim) noexcept
- bool check_no_duplicates (std::vector < idx > v)
- bool check_subsys_match_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)
- template<typename Derived >

bool check_qubit_matrix (const Eigen::MatrixBase< Derived > &A) noexcept

 $\bullet \ \ \mathsf{template}{<}\mathsf{typename} \ \mathsf{Derived}>$

 $bool\ check_qubit_cvector\ (const\ Eigen::MatrixBase < Derived > \&A)\ noexcept$

template<typename Derived >

bool check_qubit_rvector (const Eigen::MatrixBase< Derived > &A) noexcept

• template<typename Derived >

 $bool\ check_qubit_vector\ (const\ Eigen::MatrixBase < Derived > \&A)\ no except$

- bool check_perm (const std::vector< idx > &perm)
- template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > kron2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::←
 MatrixBase< Derived2 > &B)

```
    template<typename Derived1 , typename Derived2 > dyn_mat< typename Derived1::Scalar > dirsum2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen → ::MatrixBase< Derived2 > &B)
    template<typename T > void variadic_vector_emplace (std::vector< T > &)
    template<typename T , typename First , typename... Args> void variadic_vector_emplace (std::vector< T > &v, First &&first, Args &&... args)
    idx get_num_subsys (idx D, idx d)
```

6.4.1 Detailed Description

idx get_dim_subsys (idx sz, idx N)

Internal utility functions, do not use them directly or modify them.

6.4.2 Function Documentation

6.4.2.1 check_cvector()

6.4.2.2 check_dims()

```
bool qpp::internal::check_dims (  \mbox{const std::vector} < \mbox{idx} > \& \mbox{dims} \mbox{)} \quad \mbox{[inline]}
```

6.4.2.3 check_dims_match_cvect()

6.4.2.4 check_dims_match_mat()

```
6.4.2.5 check_dims_match_rvect()
```

```
template<typename Derived >
bool qpp::internal::check_dims_match_rvect (
             const std::vector< idx > & dims,
             const Eigen::MatrixBase< Derived > & A )
6.4.2.6 check_eq_dims()
bool qpp::internal::check_eq_dims (
            const std::vector< idx > & dims,
             idx dim ) [inline], [noexcept]
6.4.2.7 check_matching_sizes()
template<typename T1 , typename T2 >
bool qpp::internal::check_matching_sizes (
            const T1 & lhs,
            const T2 & rhs ) [noexcept]
6.4.2.8 check_no_duplicates()
bool qpp::internal::check_no_duplicates (
             std::vector < idx > v) [inline]
6.4.2.9 check_nonzero_size()
template<typename T >
bool qpp::internal::check_nonzero_size (
            const T & x ) [noexcept]
6.4.2.10 check_perm()
bool qpp::internal::check_perm (
```

const std::vector< idx > & perm) [inline]

6.4.2.11 check_qubit_cvector()

```
template<typename Derived >
bool qpp::internal::check_qubit_cvector (
             const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.12 check_qubit_matrix()
template<typename Derived >
bool qpp::internal::check_qubit_matrix (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.13 check_qubit_rvector()
template<typename Derived >
bool qpp::internal::check_qubit_rvector (
             const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.14 check_qubit_vector()
template < typename Derived >
bool qpp::internal::check_qubit_vector (
             const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.15 check_rvector()
template<typename Derived >
bool qpp::internal::check_rvector (
             const Eigen::MatrixBase< Derived > & A )
6.4.2.16 check_square_mat()
template < typename Derived >
bool qpp::internal::check_square_mat (
            const Eigen::MatrixBase< Derived > & A )
```

```
6.4.2.17 check_subsys_match_dims()
```

```
bool qpp::internal::check_subsys_match_dims (
            const std::vector< idx > & subsys,
            const std::vector< idx > & dims ) [inline]
6.4.2.18 check_vector()
template<typename Derived >
bool qpp::internal::check_vector (
            const Eigen::MatrixBase< Derived > & A )
6.4.2.19 dirsum2()
template<typename Derived1 , typename Derived2 >
dyn_mat<typename Derived1::Scalar> qpp::internal::dirsum2 (
            const Eigen::MatrixBase< Derived1 > & A,
            const Eigen::MatrixBase< Derived2 > & B )
6.4.2.20 get_dim_subsys()
idx qpp::internal::get_dim_subsys (
            idx sz,
            idx N ) [inline]
6.4.2.21 get_num_subsys()
idx qpp::internal::get_num_subsys (
            idx D,
            idx d ) [inline]
6.4.2.22 hash_combine()
template<class T >
void qpp::internal::hash_combine (
            std::size_t & seed,
            const T & v )
```

6.4.2.23 kron2()

```
template<typename Derived1 , typename Derived2 >
dyn_mat<typename Derived1::Scalar> qpp::internal::kron2 (
             const Eigen::MatrixBase< Derived1 > & A,
             const Eigen::MatrixBase< Derived2 > & B )
6.4.2.24 multiidx2n()
idx qpp::internal::multiidx2n (
             const idx *const midx,
             idx numdims,
             const idx *const dims ) [inline], [noexcept]
6.4.2.25 n2multiidx()
void qpp::internal::n2multiidx (
             idx n,
             idx numdims,
             const idx *const dims,
             idx * result ) [inline], [noexcept]
6.4.2.26 variadic_vector_emplace() [1/2]
template<typename T >
void qpp::internal::variadic_vector_emplace (
            std::vector< T > & )
6.4.2.27 variadic_vector_emplace() [2/2]
template<typename T , typename First , typename... Args>
void qpp::internal::variadic_vector_emplace (
             std::vector< T > & v,
             First && first,
             Args &&... args )
```

6.5 qpp::literals Namespace Reference

Functions

```
• constexpr cplx operator"" _i (unsigned long long int x) noexcept \textit{User-defined literal for complex } i = \sqrt{-1} \textit{ (integer overload)}
```

```
template<char... Bits>
ket operator"" _ket ()
```

Multi-partite qubit ket user-defined literal.

template<char... Bits> bra operator"" _bra ()

Multi-partite qubit bra user-defined literal.

template<char... Bits> cmat operator"" _prj ()

Multi-partite qubit projector user-defined literal.

6.5.1 Function Documentation

```
6.5.1.1 operator"""_bra()

template<char... Bits>
bra qpp::literals::operator"" _bra ( )
```

Multi-partite qubit bra user-defined literal.

See also

```
qpp::mket() and qpp::adjoint()
```

Constructs the multi-partite qubit bra $\langle \mathrm{Bits}|$

Template Parameters

```
Bits String of binary numbers representing the qubit bra
```

Returns

Multi-partite qubit bra, as a complex dynamic row vector

User-defined literal for complex $i = \sqrt{-1}$ (integer overload)

Example:

```
cplx z = 4_i; // type of z is std::complex<double>
```

6.5.1.3 operator""" _ket()

```
template<char... Bits>
ket qpp::literals::operator"" _ket ( )
```

Multi-partite qubit ket user-defined literal.

See also

qpp::mket()

Constructs the multi-partite qubit ket $|Bits\rangle$

Template Parameters

Bits	String of binary numbers representing the qubit ket
------	---

Returns

Multi-partite qubit ket, as a complex dynamic column vector

6.5.1.4 operator""" _prj()

```
template<char... Bits>
cmat qpp::literals::operator"" _prj ( )
```

Multi-partite qubit projector user-defined literal.

See also

qpp::mprj()

Constructs the multi-partite qubit projector $|\mathrm{Bits}\rangle\langle\mathrm{Bits}|$ (in the computational basis)

Template Parameters

Bits String of binary numbers representing the qubit state to project on

\mathbf{L}	ΔT	 rn	c

Multi-partite qubit projector, as a complex dynamic matrix

Chapter 7

Class Documentation

7.1 qpp::Bit_circuit Class Reference


Classical reversible circuit simulator.

#include <classes/reversible.h>

Inheritance diagram for qpp::Bit_circuit:



Collaboration diagram for qpp::Bit_circuit:



Classes

• struct Gate_count

Public Member Functions

- Bit_circuit (const Dynamic_bitset &dynamic_bitset)
 - Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.
- Bit_circuit & X (idx pos)

Bit flip.

Bit_circuit & NOT (idx pos)

Bit flip

• Bit_circuit & CNOT (const std::vector< idx > &pos)

Controlled-NOT.

• Bit_circuit & TOF (const std::vector< idx > &pos)

Toffoli gate.

Bit_circuit & SWAP (const std::vector < idx > &pos)

Swap bits.

• Bit_circuit & FRED (const std::vector< idx > &pos)

Fredkin gate (Controlled-SWAP)

• Bit_circuit & reset () noexcept

Reset the circuit all zero, clear all gates.

• Dynamic_bitset (idx N)

Inherited constructor.

Public Attributes

struct qpp::Bit_circuit::Gate_count gate_count
 Gate counters.

Additional Inherited Members

7.1.1 Detailed Description

Classical reversible circuit simulator.

7.1.2 Constructor & Destructor Documentation

7.1.2.1 Bit_circuit()

Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.

Parameters

7.1.3 Member Function Documentation

7.1.3.1 CNOT()

Controlled-NOT.

Parameters

```
pos Bit position in the circuit
```

Returns

Reference to the current instance

7.1.3.2 Dynamic_bitset()

```
qpp::Dynamic_bitset::Dynamic_bitset [inline], [explicit]
```

Inherited constructor.

7.1.3.3 FRED()

Fredkin gate (Controlled-SWAP)

Parameters

pos Bit positions in the circuit, in the order control-target-target

Returns

Reference to the current instance

7.1.3.4 NOT()

```
Bit_circuit& qpp::Bit_circuit::NOT (
        idx pos ) [inline]
```

Bit flip.

See also

qpp::Bit_circuit::X()

Parameters

pos Bit position in the circuit

Returns

Reference to the current instance

7.1.3.5 reset()

```
Bit_circuit& qpp::Bit_circuit::reset ( ) [inline], [noexcept]
```

Reset the circuit all zero, clear all gates.

Returns

Reference to the current instance

7.1.3.6 SWAP()

Swap bits.

Parameters

pos Bit positions in the circuit

Returns

Reference to the current instance

7.1.3.7 TOF()

Toffoli gate.

Parameters

pos | Bit positions in the circuit, in the order control-control-target

Returns

Reference to the current instance

7.1.3.8 X()

```
Bit_circuit& qpp::Bit_circuit::X (
        idx pos ) [inline]
```

Bit flip.

See also

qpp::Bit_circuit::NOT()

Parameters

pos Bit position in the circuit

Returns

Reference to the current instance

7.1.4 Member Data Documentation

7.1.4.1 gate_count

```
struct qpp::Bit_circuit::Gate_count qpp::Bit_circuit::gate_count
```

Gate counters.

The documentation for this class was generated from the following file:


• classes/reversible.h

7.2 qpp::Codes Class Reference


const Singleton class that defines quantum error correcting codes

```
#include <classes/codes.h>
```

Inheritance diagram for qpp::Codes:



Collaboration diagram for qpp::Codes:



Public Types

• enum Type { Type::FIVE_QUBIT = 1, Type::SEVEN_QUBIT_STEANE, Type::NINE_QUBIT_SHOR }

Code types, add more codes here if needed.

Public Member Functions

ket codeword (Type type, idx i) const
 Returns the codeword of the specified code type.

Private Member Functions

• Codes ()

Default constructor.

∼Codes ()=default

Default destructor.

Friends

class internal::Singleton < const Codes >

Additional Inherited Members

7.2.1 Detailed Description

const Singleton class that defines quantum error correcting codes

7.2.2 Member Enumeration Documentation

7.2.2.1 Type

```
enum qpp::Codes::Type [strong]
```

Code types, add more codes here if needed.

See also

```
qpp::Codes::codeword()
```

Enumerator

FIVE_QUBIT	[[5,1,3]] qubit code
SEVEN_QUBIT_STEANE	[[7,1,3]] Steane qubit code
NINE_QUBIT_SHOR	[[9,1,3]] Shor qubit code

7.2.3 Constructor & Destructor Documentation

7.2.3.1 Codes()

```
qpp::Codes::Codes ( ) [inline], [private]
```

Default constructor.

7.2.3.2 ∼Codes()

```
qpp::Codes::~Codes ( ) [private], [default]
```

Default destructor.

7.2.4 Member Function Documentation

7.2.4.1 codeword()

Returns the codeword of the specified code type.

See also

qpp::Codes::Type

Parameters

type	Code type
i	Codeword index

Returns

i-th codeword of the code type

7.2.5 Friends And Related Function Documentation

7.2.5.1 internal::Singleton < const Codes >

```
friend class internal::Singleton< const Codes > [friend]
```

The documentation for this class was generated from the following file:

classes/codes.h

7.3 qpp::exception::CustomException Class Reference


Custom exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::CustomException:



Collaboration diagram for qpp::exception::CustomException:



Public Member Functions

· CustomException (const std::string &where, const std::string &what)

Private Member Functions

std::string type_description () const override
 Exception type description.

Private Attributes

std::string what_{{}}

7.3.1 Detailed Description

Custom exception.

Custom exception, the user must provide a custom message

7.3.2 Constructor & Destructor Documentation

7.3.2.1 CustomException()

7.3.3 Member Function Documentation

7.3.3.1 type_description()

```
std::string qpp::exception::CustomException::type_description ( ) const [inline], [override],
[private], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

7.3.4 Member Data Documentation

7.3.4.1 what_

```
std::string qpp::exception::CustomException::what_ {} [private]
```

The documentation for this class was generated from the following file:


· classes/exception.h

7.4 qpp::exception::DimsInvalid Class Reference

Invalid dimension(s) exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsInvalid:



Collaboration diagram for qpp::exception::DimsInvalid:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.4.1 Detailed Description

Invalid dimension(s) exception.

std::vector<idx> of dimensions has zero size or contains zeros

7.4.2 Member Function Documentation

7.4.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.4.2.2 type_description()

std::string qpp::exception::DimsInvalid::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.5 qpp::exception::DimsMismatchCvector Class Reference


Dimension(s) mismatch column vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchCvector:



Collaboration diagram for qpp::exception::DimsMismatchCvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.5.1 Detailed Description

Dimension(s) mismatch column vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a column vector)

7.5.2 Member Function Documentation

7.5.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
******	Toxt representing where the exception eccurred

7.5.2.2 type_description()

std::string qpp::exception::DimsMismatchCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.6 qpp::exception::DimsMismatchMatrix Class Reference


Dimension(s) mismatch matrix size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchMatrix:



Collaboration diagram for qpp::exception::DimsMismatchMatrix:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.6.1 Detailed Description

Dimension(s) mismatch matrix size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of rows of the Eigen::Matrix (assumed to be a square matrix)

7.6.2 Member Function Documentation

7.6.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred
--

7.6.2.2 type_description()

```
std::string qpp::exception::DimsMismatchMatrix::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

7.7 qpp::exception::DimsMismatchRvector Class Reference


Dimension(s) mismatch row vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchRvector:



Collaboration diagram for qpp::exception::DimsMismatchRvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.7.1 Detailed Description

Dimension(s) mismatch row vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row vector)

7.7.2 Member Function Documentation

7.7.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

Text representing where the exception of	d
--	---

7.7.2.2 type_description()

std::string qpp::exception::DimsMismatchRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

7.8 qpp::exception::DimsMismatchVector Class Reference

Dimension(s) mismatch vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchVector:



Collaboration diagram for qpp::exception::DimsMismatchVector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.8.1 Detailed Description

Dimension(s) mismatch vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row/column vector)

7.8.2 Member Function Documentation

7.8.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
******	Toxt representing where the exception eccurred

7.8.2.2 type_description()

```
std::string qpp::exception::DimsMismatchVector::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.9 qpp::exception::DimsNotEqual Class Reference


Dimensions not equal exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsNotEqual:



Collaboration diagram for qpp::exception::DimsNotEqual:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.9.1 Detailed Description

Dimensions not equal exception.

Local/global dimensions are not equal

7.9.2 Member Function Documentation

7.9.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.9.2.2 type_description()

std::string qpp::exception::DimsNotEqual::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

7.10 qpp::internal::Display_Impl_ Struct Reference

```
#include <internal/util.h>
```

Inheritance diagram for qpp::internal::Display_Impl_:



Public Member Functions

template<typename T >
 std::ostream & display_impl_ (const T &A, std::ostream &os, double chop=qpp::chop) const

7.10.1 Member Function Documentation

7.10.1.1 display_impl_()

The documentation for this struct was generated from the following file:


• internal/util.h

7.11 qpp::exception::Duplicates Class Reference


System (e.g. std::vector) has duplicates exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Duplicates:



Collaboration diagram for qpp::exception::Duplicates:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.11.1 Detailed Description

System (e.g. std::vector) has duplicates exception.

7.11.2 Member Function Documentation

7.11.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.11.2.2 type_description()

```
std::string qpp::exception::Duplicates::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.12 qpp::Dynamic_bitset Class Reference

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std:bitset < N >)

#include <classes/reversible.h>

Inheritance diagram for qpp::Dynamic_bitset:



Collaboration diagram for qpp::Dynamic_bitset:



Public Types

- using value_type = unsigned int
 Type of the storage elements.
- using storage_type = std::vector< value_type >
 Type of the storage.

Public Member Functions

• Dynamic bitset (idx N)

Constructor, initializes all bits to false (zero)

virtual ~Dynamic bitset ()=default

Default virtual destructor.

const storage_type & data () const

Raw storage space of the bitset.

• idx size () const noexcept

Number of bits stored in the bitset.

• idx storage_size () const noexcept

Size of the underlying storage space (in units of value_type, unsigned int by default)

· idx count () const noexcept

Number of bits set to one in the bitset (Hamming weight)

bool get (idx pos) const noexcept

The value of the bit at position pos.

· bool none () const noexcept

Checks whether none of the bits are set.

• bool all () const noexcept

Checks whether all bits are set.

• bool any () const noexcept

Checks whether any bit is set.

Dynamic_bitset & set (idx pos, bool value=true)

Sets the bit at position pos.

Dynamic_bitset & set () noexcept

Set all bits to true.

• Dynamic bitset & rand (idx pos, double p=0.5)

Sets the bit at position pos according to a Bernoulli(p) distribution.

• Dynamic_bitset & rand (double p=0.5)

Sets all bits according to a Bernoulli(p) distribution.

Dynamic_bitset & reset (idx pos)

Sets the bit at position pos to false.

Dynamic_bitset & reset () noexcept

Sets all bits to false.

Dynamic_bitset & flip (idx pos)

Flips the bit at position pos.

· Dynamic bitset & flip () noexcept

Flips all bits.

• bool operator== (const Dynamic_bitset &rhs) const noexcept

Equality operator.

• bool operator!= (const Dynamic_bitset &rhs) const noexcept

Inequality operator.

• idx operator- (const Dynamic_bitset &rhs) const noexcept

Number of places the two bitsets differ (Hamming distance)

template < class CharT = char, class Traits = std::char_traits < CharT>, class Allocator = std::allocator < CharT>> std::basic_string < CharT, Traits, Allocator > to_string (CharT zero=CharT('0'), CharT one=CharT('1')) const String representation.

Protected Member Functions

- idx index_ (idx pos) const
 Index of the pos bit in the storage space.
- idx offset_ (idx pos) const

Offset of the pos bit in the storage space relative to its index.

Protected Attributes

```
• idx storage_size_
Storage size.
```

idx N

Number of bits.

std::vector< value_type > v_
 Storage space.

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display()* override, displays the bitset bit by bit

7.12.1 Detailed Description

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

7.12.2 Member Typedef Documentation

```
7.12.2.1 storage_type
```

```
using qpp::Dynamic_bitset::storage_type = std::vector<value_type>
```

Type of the storage.

7.12.2.2 value_type

```
using qpp::Dynamic_bitset::value_type = unsigned int
```

Type of the storage elements.

7.12.3 Constructor & Destructor Documentation

7.12.3.1 Dynamic_bitset()

Constructor, initializes all bits to false (zero)

Parameters

N Number of bits in the bitset

```
7.12.3.2 ~Dynamic_bitset()
```

```
virtual qpp::Dynamic_bitset::~Dynamic_bitset ( ) [virtual], [default]
```

Default virtual destructor.

7.12.4 Member Function Documentation

```
7.12.4.1 all()
```

```
bool qpp::Dynamic_bitset::all ( ) const [inline], [noexcept]
```

Checks whether all bits are set.

Returns

True if all of the bits are set

7.12.4.2 any()

```
bool qpp::Dynamic_bitset::any ( ) const [inline], [noexcept]
```

Checks whether any bit is set.

Returns

True if any of the bits is set

7.12.4.3 count()

```
idx qpp::Dynamic_bitset::count ( ) const [inline], [noexcept]
```

Number of bits set to one in the bitset (Hamming weight)

Returns

Hamming weight

7.12.4.4 data()

```
const storage_type& qpp::Dynamic_bitset::data ( ) const [inline]
```

Raw storage space of the bitset.

Returns

Const reference to the underlying storage space

7.12.4.5 display()

qpp::IDisplay::display() override, displays the bitset bit by bit

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.12.4.6 flip() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip (
        idx pos ) [inline]
```

Flips the bit at position pos.

Parameters

pos Position in the bitset

Returns

Reference to the current instance

```
7.12.4.7 flip() [2/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip ( ) [inline], [noexcept]
```

Flips all bits.

Returns

Reference to the current instance

7.12.4.8 get()

```
bool qpp::Dynamic_bitset::get (
          idx pos ) const [inline], [noexcept]
```

The value of the bit at position pos.

Parameters

pos	Position in the bitset
-----	------------------------

Returns

The value of the bit at position pos

7.12.4.9 index_()

Index of the pos bit in the storage space.

Parameters

```
pos Bit location
```

Returns

Index of the pos bit in the storage space

7.12.4.10 none()

```
bool qpp::Dynamic_bitset::none ( ) const [inline], [noexcept]
```

Checks whether none of the bits are set.

Returns

True if none of the bits are set

7.12.4.11 offset_()

Offset of the *pos* bit in the storage space relative to its index.

Parameters

```
pos Bit location
```

Returns

Offset of the pos bit in the storage space relative to its index

7.12.4.12 operator"!=()

Inequality operator.

Parameters

```
rhs Dynamic_bitset against which the inequality is being tested
```

Returns

True if the bitsets are not equal (bit by bit), false otherwise

7.12.4.13 operator-()

Number of places the two bitsets differ (Hamming distance)

Parameters

```
rhs Dynamic_bitset against which the Hamming distance is computed
```

Returns

Hamming distance

7.12.4.14 operator==()

Equality operator.

Parameters

```
rhs Dynamic_bitset against which the equality is being tested
```

Returns

True if the bitsets are equal (bit by bit), false otherwise

7.12.4.15 rand() [1/2]

```
Dynamic_bitset& qpp::Dynamic_bitset::rand (
    idx pos,
    double p = 0.5 ) [inline]
```

Sets the bit at position *pos* according to a Bernoulli(p) distribution.

Parameters

pos	Position in the bitset
р	Probability

Returns

Reference to the current instance

Sets all bits according to a Bernoulli(p) distribution.

Parameters

```
p Probability
```

Returns

Reference to the current instance

Sets the bit at position pos to false.

Parameters

```
pos Position in the bitset
```

Returns

Reference to the current instance

```
7.12.4.18 reset() [2/2]
Dynamic_bitset& qpp::Dynamic_bitset::reset ( ) [inline], [noexcept]
Sets all bits to false.
```

Returns

Reference to the current instance

```
7.12.4.19 set() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::set (
        idx pos,
        bool value = true ) [inline]
```

Sets the bit at position pos.

Parameters

pos	Position in the bitset
value	Bit value

Returns

Reference to the current instance

```
7.12.4.20 set() [2/2]
Dynamic_bitset& qpp::Dynamic_bitset::set ( ) [inline], [noexcept]
```

Set all bits to true.

Returns

Reference to the current instance

```
7.12.4.21 size()
```

```
idx qpp::Dynamic_bitset::size ( ) const [inline], [noexcept]
```

Number of bits stored in the bitset.

Returns

Number of bits stored in the bitset

```
7.12.4.22 storage_size()
```

```
idx qpp::Dynamic_bitset::storage_size ( ) const [inline], [noexcept]
```

Size of the underlying storage space (in units of value_type, unsigned int by default)

Returns

Size of the underlying storage space

7.12.4.23 to_string()

String representation.

Template Parameters

CharT	String character type
Traits	String traits
Allocator	String Allocator

Parameters

	Character representing the zero
one	Character representing the one

Returns

The bitset as a string

7.12.5 Member Data Documentation

```
7.12.5.1 N_
```

```
idx qpp::Dynamic_bitset::N_ [protected]
```

Number of bits.


7.12.5.2 storage_size_

```
idx qpp::Dynamic_bitset::storage_size_ [protected]
```

Storage size.

166	Class Documentation
7.12.5.3 v_	
<pre>std::vector<value_type> qpp::Dynamic_bitset::v_ [protected]</value_type></pre>	
Storage space.	
The documentation for this class was generated from the following file:	
• classes/reversible.h	
7.13 qpp::exception::Exception Class Reference	
Base class for generating Quantum++ custom exceptions.	
<pre>#include <classes exception.h=""></classes></pre>	

Inheritance diagram for qpp::exception::Exception:



Collaboration diagram for qpp::exception::Exception:



Public Member Functions

• Exception (const std::string &where)

Constructs an exception.

- virtual const char * what () const noexcept override

Overrides std::exception::what()

• virtual std::string type_description () const =0

Exception type description.

Private Attributes

- std::string where_
- std::string msg_

7.13.1 Detailed Description

Base class for generating Quantum++ custom exceptions.

Derive from this class if more exceptions are needed, making sure to override qpp::exception::Exception::type_description() in the derived class and to inherit the constructor qpp::exception::Exception::Exception(). Preferably keep your newly defined exception classes in the namespace qpp::exception.

Example:

7.13.2 Constructor & Destructor Documentation

7.13.2.1 Exception()

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.13.3 Member Function Documentation

7.13.3.1 type_description()

```
std::string qpp::exception::Exception::type_description ( ) const [inline], [pure virtual]
```

Exception type description.

Returns

Exception type description

Implemented in qpp::exception::InvalidIterator, qpp::exception::NotImplemented, qpp::exception::CustomException, qpp::exception::Duplicates, qpp::exception::QuditAlreadyMeasured, qpp::exception::UndefinedType, qpp::exception::SizeMismatch, qpp::exception::TypeMismatch, qpp::exception::OutOfRange, qpp::exception::NotOdeword, qpp::exception::NotBipartite, qpp::exception::NotQubitSubsys, qpp::exception::NotQubitVector, qpp::exception::NotQubitRvector, qpp::exception::NotQubitCvector qpp::exception::NotQubitMatrix, qpp::exception::PermMismatchDims, qpp::exception::PermInvalid, qpp::exception::SubsysMismatchEqpp::exception::DimsMismatchVector, qpp::exception::DimsMismatchCvector, qpp::exception::DimsMismatchMatrix, qpp::exception::DimsNotEqual, qpp::exception::DimsInvalid, qpp::exception::MatrixMismatchSu qpp::exception::MatrixNotSquareNorVector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::Unknown.

7.13.3.2 what()

virtual const char* qpp::exception::Exception::what () const [inline], [override], [virtual],
[noexcept]

Overrides std::exception::what()

Returns

Exception description

7.13.4 Member Data Documentation

```
7.13.4.1 msg_
```

std::string qpp::exception::Exception::msg_ [mutable], [private]

7.13.4.2 where_

std::string qpp::exception::Exception::where_ [private]

The documentation for this class was generated from the following file:

· classes/exception.h

7.14 qpp::Bit_circuit::Gate_count Struct Reference

```
#include <classes/reversible.h>
```

Public Attributes

- idx NOT = 0
- idx & X = NOT
- idx CNOT = 0
- idx SWAP = 0
- idx FRED = 0
- idx TOF = 0

7.14.1 Member Data Documentation

7.14.1.1 CNOT

```
idx qpp::Bit_circuit::Gate_count::CNOT = 0
```

7.14.1.2 FRED

```
idx qpp::Bit_circuit::Gate_count::FRED = 0
```

7.14.1.3 NOT

```
idx qpp::Bit_circuit::Gate_count::NOT = 0
```

7.14.1.4 SWAP

```
idx qpp::Bit_circuit::Gate_count::SWAP = 0
```

7.14.1.5 TOF

```
idx qpp::Bit_circuit::Gate_count::TOF = 0
```

7.14.1.6 X

```
idx& qpp::Bit_circuit::Gate_count::X = NOT
```

The documentation for this struct was generated from the following file:

• classes/reversible.h

7.15 qpp::Gates Class Reference


const Singleton class that implements most commonly used gates

#include <classes/gates.h>

Inheritance diagram for qpp::Gates:



Collaboration diagram for qpp::Gates:



Public Member Functions

- cmat Rn (double theta, const std::vector< double > &n) const
 Qubit rotation of theta about the 3-dimensional real (unit) vector n.
- cmat RX (double theta) const

Qubit rotation of theta about the X axis.

• cmat RY (double theta) const

Qubit rotation of theta about the Y axis.

cmat RZ (double theta) const

Qubit rotation of theta about the Z axis.

• cmat Zd (idx D=2) const

Generalized Z gate for qudits.

```
• cmat SWAPd (idx D=2) const
          SWAP gate for qudits.
    • cmat Fd (idx D=2) const
          Quantum Fourier transform gate for qudits.

    cmat MODMUL (idx a, idx N, idx n) const

          Modular multiplication gate for qubits Implements |x\rangle \longrightarrow |ax \bmod N\rangle.

    cmat Xd (idx D=2) const

          Generalized X gate for qudits.
    • template<typename Derived = Eigen::MatrixXcd>
      Derived Id (idx D=2) const
          Identity gate.

    template<typename Derived >

      dyn mat< typename Derived::Scalar > CTRL (const Eigen::MatrixBase< Derived > &A, const std::vector<
      idx > &ctrl, const std::vector < idx > &target, idx n, idx d=2) const
          Generates the multi-partite multiple-controlled-A gate in matrix form.

    template<typename Derived >

      dyn mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
      std::vector < idx > &dims) const
          Expands out.

    template<typename Derived >

      dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
      std::initializer list< idx > &dims) const
          Expands out.

    template<typename Derived >

      dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, idx n,
      idx d=2) const
          Expands out.
    • std::string get_name (const cmat &U) const
          Get the name of the most common qubit gates.
Public Attributes
    cmat Id2 {cmat::Identity(2, 2)}
          Identity gate.

    cmat H {cmat::Zero(2, 2)}

          Hadamard gate.
    cmat X {cmat::Zero(2, 2)}
          Pauli Sigma-X gate.

    cmat Y {cmat::Zero(2, 2)}

          Pauli Sigma-Y gate.

    cmat Z {cmat::Zero(2, 2)}

          Pauli Sigma-Z gate.

    cmat S {cmat::Zero(2, 2)}

          S gate.

    cmat T {cmat::Zero(2, 2)}

          T gate.

    cmat CNOT {cmat::Identity(4, 4)}

          Controlled-NOT control target gate.

    cmat CZ {cmat::Identity(4, 4)}

          Controlled-Phase gate.

    cmat CNOTba {cmat::Zero(4, 4)}
```

```
Controlled-NOT target->control gate.
```

• cmat SWAP {cmat::Identity(4, 4)}

SWAP gate.

• cmat TOF {cmat::ldentity(8, 8)}

Toffoli gate.

• cmat FRED {cmat::ldentity(8, 8)}

Fredkin gate.

Private Member Functions

• Gates ()

Initializes the gates.

∼Gates ()=default

Default destructor.

Friends

class internal::Singleton < const Gates >

Additional Inherited Members

7.15.1 Detailed Description

const Singleton class that implements most commonly used gates

7.15.2 Constructor & Destructor Documentation

```
7.15.2.1 Gates()
```

```
qpp::Gates::Gates ( ) [inline], [private]
```

Initializes the gates.

7.15.2.2 \sim Gates()

```
qpp::Gates::\sim Gates ( ) [private], [default]
```

Default destructor.

7.15.3 Member Function Documentation

7.15.3.1 CTRL()

Generates the multi-partite multiple-controlled-A gate in matrix form.

See also

```
qpp::applyCTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
n	Total number of subsystems
d	Subsystem dimensions

Returns

CTRL-A gate, as a matrix over the same scalar field as A

7.15.3.2 expandout() [1/3]

Expands out.

See also

```
qpp::kron()
```

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

	Α	Eigen expression
	pos	Position
ĺ	dims	Dimensions of the multi-partite system

Returns

Tensor product $I\otimes\cdots\otimes I\otimes A\otimes I\otimes\cdots\otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

```
7.15.3.3 expandout() [2/3]
```

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Note

The std::initializer_list overload exists because otherwise, in the degenerate case when *dims* has only one element, the one element list is implicitly converted to the element's underlying type, i.e. qpp::idx, which has the net effect of picking the wrong (non-vector) qpp::expandout() overload

Parameters

Α	Eigen expression
pos	Position
dims	Dimensions of the multi-partite system

Returns

Tensor product $I\otimes\cdots\otimes I\otimes A\otimes I\otimes\cdots\otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.15.3.4 expandout() [3/3]

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

Α	Eigen expression
pos	Position
n	Number of subsystems
d	Subsystem dimensions

Returns

Tensor product $I \otimes \cdots \otimes I \otimes A \otimes I \otimes \cdots \otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.15.3.5 Fd()

```
cmat qpp::Gates::Fd (
    idx D = 2 ) const [inline]
```

Quantum Fourier transform gate for qudits.

Note

Defined as
$$F = \sum_{j,k=0}^{D-1} \exp(2\pi \mathrm{i} jk/D) |j\rangle\langle k|$$

Parameters

D Dimension of the Hilbert space

Returns

Fourier transform gate for qudits

7.15.3.6 get_name()

Get the name of the most common qubit gates.

Note

Assumes that the gate U is represented by a square matrix. If not, returns the empty string

Parameters

U | Complex matrix representing the quantum gate

Returns

The name of the gate (if any), otherwise the empty string

7.15.3.7 ld()

```
template<typename Derived = Eigen::MatrixXcd>
Derived qpp::Gates::Id (
    idx D = 2 ) const [inline]
```

Identity gate.

Note

Can change the return type from complex matrix (default) by explicitly specifying the template parameter

Parameters

D Dimension of the Hilbert space

Returns

Identity gate on a Hilbert space of dimension D

7.15.3.8 MODMUL()

```
cmat qpp::Gates::MODMUL (
    idx a,
```

```
idx N, idx n) const [inline]
```

Modular multiplication gate for qubits Implements $|x\rangle \longrightarrow |ax \bmod N\rangle$.

Note

For the gate to be unitary, *a* and *N* should be co-prime. The function does not check co-primality in release versions!

The number of qubits required to implement the gate should satisfy $n \geq \lceil \log_2(N) \rceil$

Parameters

а	Positive integer less than N
Ν	Positive integer
n	Number of qubits required for implementing the gate

Returns

Modular multiplication gate

7.15.3.9 Rn()

Qubit rotation of *theta* about the 3-dimensional real (unit) vector *n*.

Parameters

theta	Rotation angle
n	3-dimensional real (unit) vector

Returns

Rotation gate

7.15.3.10 RX()

Qubit rotation of theta about the X axis.

Parameters

theta	Rotation angle
-------	----------------

Returns

Rotation gate

7.15.3.11 RY()

Qubit rotation of *theta* about the Y axis.

Parameters

Returns

Rotation gate

7.15.3.12 RZ()

Qubit rotation of theta about the Z axis.

Parameters

```
theta Rotation angle
```

Returns

Rotation gate

7.15.3.13 SWAPd()

```
cmat qpp::Gates::SWAPd (
        idx D = 2 ) const [inline]
```

SWAP gate for qudits.

Parameters

D Dimension of the Hilbert space

Returns

SWAP gate for qudits

7.15.3.14 Xd()

```
cmat qpp::Gates::Xd (
    idx D = 2 ) const [inline]
```

Generalized X gate for qudits.

Note

```
Defined as X=\sum_{j=0}^{D-1}|j\oplus 1\rangle\langle j|, i.e. raising operator X|j\rangle=|j\oplus 1\rangle
```

Parameters

D Dimension of the Hilbert space

Returns

Generalized X gate for qudits

7.15.3.15 Zd()

```
cmat qpp::Gates::Zd (
    idx D = 2 ) const [inline]
```

Generalized Z gate for qudits.

Note

Defined as
$$Z = \sum_{j=0}^{D-1} \exp(2\pi \mathrm{i} j/D) |j\rangle\langle j|$$

Parameters

D Dimension of the Hilbert space

Returns

Generalized Z gate for qudits

7.15.4 Friends And Related Function Documentation

```
7.15.4.1 internal::Singleton < const Gates >
friend class internal::Singleton < const Gates > [friend]
```

7.15.5 Member Data Documentation

```
7.15.5.1 CNOT
```

```
cmat qpp::Gates::CNOT {cmat::Identity(4, 4)}
```

Controlled-NOT control target gate.

7.15.5.2 CNOTba

```
cmat qpp::Gates::CNOTba {cmat::Zero(4, 4)}
```

Controlled-NOT target->control gate.

7.15.5.3 CZ

```
cmat qpp::Gates::CZ {cmat::Identity(4, 4)}
```

Controlled-Phase gate.

7.15.5.4 FRED

```
cmat qpp::Gates::FRED {cmat::Identity(8, 8)}
```

Fredkin gate.

```
7.15.5.5 H
cmat qpp::Gates::H {cmat::Zero(2, 2)}
Hadamard gate.
7.15.5.6 ld2
cmat qpp::Gates::Id2 {cmat::Identity(2, 2)}
Identity gate.
7.15.5.7 S
cmat qpp::Gates::S {cmat::Zero(2, 2)}
S gate.
7.15.5.8 SWAP
cmat qpp::Gates::SWAP {cmat::Identity(4, 4)}
SWAP gate.
7.15.5.9 T
cmat qpp::Gates::T {cmat::Zero(2, 2)}
T gate.
7.15.5.10 TOF
cmat qpp::Gates::TOF {cmat::Identity(8, 8)}
Toffoli gate.
```

7.15.5.11 X

```
cmat qpp::Gates::X {cmat::Zero(2, 2)}
```

Pauli Sigma-X gate.

7.15.5.12 Y

```
cmat qpp::Gates::Y {cmat::Zero(2, 2)}
```

Pauli Sigma-Y gate.

7.15.5.13 Z

```
cmat qpp::Gates::Z {cmat::Zero(2, 2)}
```

Pauli Sigma-Z gate.

The documentation for this class was generated from the following file:


· classes/gates.h

7.16 qpp::QCircuit::GateStep Struct Reference

One step consisting only of gates/operators in the circuit.

```
#include <classes/circuits.h>
```

Collaboration diagram for qpp::QCircuit::GateStep:



Public Member Functions

• GateStep ()=default

Default constructor.

GateStep (GateType gate_type, const cmat &gate, const std::vector< idx > &ctrl, const std::vector< idx > &target, std::string name="")

Constructs a gate step instance.

Public Attributes

```
    GateType gate_type_ = GateType::NONE
        gate type
    cmat gate_
        gate
    std::vector < idx > ctrl_
        control
    std::vector < idx > target_
        target where the gate is applied
    std::string name_
        custom name of the step
```

7.16.1 Detailed Description

7.16.2.1 GateStep() [1/2]

One step consisting only of gates/operators in the circuit.

7.16.2 Constructor & Destructor Documentation

Constructs a gate step instance.

Parameters

gate_type	Gate type
gate	Quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes
step_no	Circuit step number
name	Optional gate name

7.16.3 Member Data Documentation

```
7.16.3.1 ctrl_
std::vector<idx> qpp::QCircuit::GateStep::ctrl_
control
7.16.3.2 gate_
cmat qpp::QCircuit::GateStep::gate_
gate
7.16.3.3 gate_type_
GateType qpp::QCircuit::GateStep::gate_type_ = GateType::NONE
gate type
7.16.3.4 name_
std::string qpp::QCircuit::GateStep::name_
```

custom name of the step

7.16.3.5 target_

```
std::vector<idx> qpp::QCircuit::GateStep::target_
```

target where the gate is applied

The documentation for this struct was generated from the following file:

· classes/circuits.h

7.17 qpp::internal::HashEigen Class Reference

Functor for hashing Eigen expressions.

```
#include <functions.h>
```

Public Member Functions

```
    template<typename Derived >
        std::size_t operator() (const Eigen::MatrixBase< Derived > &A) const
```

7.17.1 Detailed Description

Functor for hashing Eigen expressions.

7.17.2 Member Function Documentation

7.17.2.1 operator()()

The documentation for this class was generated from the following file:


· functions.h

7.18 qpp::IDisplay Class Reference

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

#include <classes/idisplay.h>

Inheritance diagram for qpp::IDisplay:



Public Member Functions

• IDisplay ()=default

Default constructor.

• IDisplay (const IDisplay &)=default

Default copy constructor.

• IDisplay (IDisplay &&)=default

Default move constructor.

• IDisplay & operator= (const IDisplay &)=default

Default copy assignment operator.

• IDisplay & operator= (IDisplay &&)=default

Default move assignment operator.

virtual ~IDisplay ()=default

Default virtual destructor.

Private Member Functions

virtual std::ostream & display (std::ostream &os) const =0
 Must be overridden by all derived classes.

Friends

std::ostream & operator<< (std::ostream &os, const IDisplay &rhs)
 Overloads the extraction operator.

7.18.1 Detailed Description

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

This class defines friend inline std::ostream& operator<< (std::ostream& os, const qpp::IDisplay& rhs). The latter delegates the work to the pure private virtual function qpp::IDisplay::display() which has to be overridden by all derived classes.

7.18.2 Constructor & Destructor Documentation

```
7.18.2.1 | Display() [1/3]

qpp::IDisplay::IDisplay ( ) [default]
```

Default constructor.

Default copy constructor.

Default move constructor.

Default virtual destructor.

```
7.18.2.4 ~IDisplay()
virtual qpp::IDisplay::~IDisplay ( ) [virtual], [default]
```

7.18.3 Member Function Documentation

7.18.3.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implemented in qpp::QEngine, qpp::QCircuit, qpp::QCircuit::iterator::value_type_, qpp::Dynamic_bitset, qpp::internal::IOManipEigen, qpp::Timer< T, CLOCK_T >, qpp::internal::IOManipPointer< PointerType >, and qpp::internal::IOManipRange< InputIterator >.

```
7.18.3.2 operator=() [1/2]
```

Default copy assignment operator.

```
7.18.3.3 operator=() [2/2]
```

Default move assignment operator.

7.18.4 Friends And Related Function Documentation

7.18.4.1 operator <<

Overloads the extraction operator.

Delegates the work to the virtual function qpp::IDisplay::display()

The documentation for this class was generated from the following file:


· classes/idisplay.h

7.19 qpp::IJSON Class Reference

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

#include <classes/idisplay.h>

Inheritance diagram for qpp::IJSON:



Public Member Functions

• IJSON ()=default

Default constructor.

• IJSON (const IJSON &)=default

Default copy constructor.

• IJSON (IJSON &&)=default

Default move constructor.

• IJSON & operator= (const IJSON &)=default

Default copy assignment operator.

• IJSON & operator= (IJSON &&)=default

Default move assignment operator.

virtual ∼IJSON ()=default

Default virtual destructor.

virtual std::string to_JSON (bool enclosed_in_curly_brackets=true) const =0

JSON representation of the derived instance, must be overridden by all derived classes.

7.19.1 Detailed Description

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

7.19.2 Constructor & Destructor Documentation

```
7.19.2.1 IJSON() [1/3]
qpp::IJSON::IJSON ( ) [default]
Default constructor.
7.19.2.2 IJSON() [2/3]
qpp::IJSON::IJSON (
             const IJSON & ) [default]
Default copy constructor.
7.19.2.3 IJSON() [3/3]
qpp::IJSON::IJSON (
              IJSON && ) [default]
Default move constructor.
7.19.2.4 ∼IJSON()
virtual qpp::IJSON::~IJSON ( ) [virtual], [default]
Default virtual destructor.
7.19.3 Member Function Documentation
7.19.3.1 operator=() [1/2]
IJSON& qpp::IJSON::operator= (
              {\tt const\ IJSON\ \&\quad)\quad [default]}
Default copy assignment operator.
7.19.3.2 operator=() [2/2]
IJSON& qpp::IJSON::operator= (
              IJSON && ) [default]
Default move assignment operator.
7.19.3.3 to_JSON()
```

JSON representation of the derived instance, must be overridden by all derived classes.

bool enclosed_in_curly_brackets = true) const [pure virtual]

virtual std::string qpp::IJSON::to_JSON (

Parameters

enclosed_in_curly_brackets If true, encloses the result in curly brackets

Implemented in qpp::QEngine, and qpp::QCircuit.

The documentation for this class was generated from the following file:


· classes/idisplay.h

7.20 qpp::Init Class Reference


const Singleton class that performs additional initializations/cleanups

#include <classes/init.h>

Inheritance diagram for qpp::Init:



Collaboration diagram for qpp::Init:



Private Member Functions

```
• Init ()
```

Additional initializations.

• ∼Init ()

Cleanups.

Friends

class internal::Singleton < const Init >

Additional Inherited Members

7.20.1 Detailed Description

const Singleton class that performs additional initializations/cleanups

7.20.2 Constructor & Destructor Documentation

```
7.20.2.1 Init()

qpp::Init::Init ( ) [inline], [private]

Additional initializations.
```

```
7.20.2.2 \simInit()  \texttt{qpp::Init::} \sim \texttt{Init ( ) [inline], [private]}  Cleanups.
```

7.20.3 Friends And Related Function Documentation

```
7.20.3.1 internal::Singleton < const lnit >
friend class internal::Singleton < const Init > [friend]
```

The documentation for this class was generated from the following file:


· classes/init.h

7.21 qpp::exception::InvalidIterator Class Reference


Invalid iterator.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::InvalidIterator:



Collaboration diagram for qpp::exception::InvalidIterator:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.21.1 Detailed Description

Invalid iterator.

7.21.2 Member Function Documentation

7.21.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.21.2.2 type_description()

```
std::string qpp::exception::InvalidIterator::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

· classes/exception.h


7.22 qpp::internal::IOManipEigen Class Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipEigen:



Collaboration diagram for qpp::internal::IOManipEigen:



Public Member Functions

- template<typename Derived > IOManipEigen (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
- IOManipEigen (const cplx z, double chop=qpp::chop)

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- · cmat A_
- · double chop_

7.22.1 Constructor & Destructor Documentation

7.22.2 Member Function Documentation

7.22.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.22.3 Member Data Documentation

7.22.3.1 A_

```
cmat qpp::internal::IOManipEigen::A_ [private]
```

7.22.3.2 chop_

```
double qpp::internal::IOManipEigen::chop_ [private]
```


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


7.23 qpp::internal::IOManipPointer< PointerType > Class Template Reference

```
#include <internal/classes/iomanip.h>
```

Inheritance diagram for qpp::internal::IOManipPointer< PointerType >:



Collaboration diagram for qpp::internal::IOManipPointer< PointerType >:



Public Member Functions

- IOManipPointer (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")
- IOManipPointer (const IOManipPointer &)=default
- IOManipPointer & operator= (const IOManipPointer &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- const PointerType * p_
- idx N_
- std::string separator_
- std::string start_
- std::string end_

7.23.1 Constructor & Destructor Documentation

7.23.1.1 IOManipPointer() [1/2]

7.23.1.2 IOManipPointer() [2/2]

7.23.2 Member Function Documentation

7.23.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.23.2.2 operator=()

7.23.3 Member Data Documentation

```
7.23.3.1 end_
```

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::end_ [private]
```

7.23.3.2 N_

```
template<typename PointerType>
idx qpp::internal::IOManipPointer< PointerType >::N_ [private]
```

7.23.3.3 p_

```
template<typename PointerType>
const PointerType* qpp::internal::IOManipPointer< PointerType >::p_ [private]
```

7.23.3.4 separator_

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::separator_ [private]
```

7.23.3.5 start_

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::start_ [private]
```


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


7.24 qpp::internal::IOManipRange < InputIterator > Class Template Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipRange< InputIterator >:



Collaboration diagram for qpp::internal::IOManipRange< InputIterator >:



Public Member Functions

- IOManipRange (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")
- IOManipRange (const IOManipRange &)=default
- IOManipRange & operator= (const IOManipRange &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- InputIterator first_
- InputIterator last
- std::string separator
- · std::string start_
- std::string end_

7.24.1 Constructor & Destructor Documentation

```
7.24.1.1 IOManipRange() [1/2]
```

7.24.1.2 IOManipRange() [2/2]

7.24.2 Member Function Documentation

7.24.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.24.2.2 operator=()

7.24.3 Member Data Documentation

```
7.24.3.1 end
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::end_ [private]
7.24.3.2 first_
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::first_ [private]
7.24.3.3 last_
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::last_ [private]
7.24.3.4 separator_
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::separator_ [private]
7.24.3.5 start_
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::start_ [private]
```

The documentation for this class was generated from the following file:

• internal/classes/iomanip.h

7.25 qpp::is_complex< T > Struct Template Reference


Checks whether the type is a complex type.

#include <traits.h>

Inheritance diagram for qpp::is_complex< T >:



Collaboration diagram for qpp::is_complex< T >:



7.25.1 Detailed Description

template<typename T> struct qpp::is_complex< T>

Checks whether the type is a complex type.

Provides the constant member *value* which is equal to *true*, if the type is a complex type, i.e. *std::complex<T>*

The documentation for this struct was generated from the following file:

7.26 qpp::is_complex < std::complex < T > > Struct Template Reference


Checks whether the type is a complex number type, specialization for complex types.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_complex < std::complex < T > :



Collaboration diagram for qpp::is_complex< std::complex< T > >:



7.26.1 Detailed Description

```
template<typename T> struct qpp::is_complex< std::complex< T > >
```

Checks whether the type is a complex number type, specialization for complex types.


The documentation for this struct was generated from the following file:

7.27 qpp::is_iterable < T, typename > Struct Template Reference


Checks whether T is compatible with an STL-like iterable container.

#include <traits.h>

Inheritance diagram for qpp::is_iterable < T, typename >:



Collaboration diagram for qpp::is_iterable < T, typename >:



7.27.1 Detailed Description

template<typename T, typename = void> struct qpp::is_iterable< T, typename >

Checks whether T is compatible with an STL-like iterable container.

Provides the constant member *value* which is equal to *true*, if *T* is compatible with an iterable container, i.e. provides at least *begin()* and *end()* member functions and allows de-referencing. Otherwise, *value* is equal to *false*.


The documentation for this struct was generated from the following file:

7.28 qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().begin())) > Struct Template Reference


Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(*(std::declval < T >().begin())) > :



 $\label{top:condition} \begin{tabular}{ll} Collaboration diagram for qpp::is_iterable< T, to_void< decltype(std::declval< T>().begin()), decltype(std::declval< T>().begin()))>>: \\ \begin{tabular}{ll} T>().begin())>>: \\ \begin{tabular}{ll} T>().begin()>>: \\ \begin{tabular}{ll} T>().begin()>: \\ \begin{tabular}{ll}$



7.28.1 Detailed Description

 $template < typename \ T > \\ struct \ qpp::is_iterable < T, \ to_void < decltype(std::declval < T > ().begin()), \ decltype(std::declval < T > ().end()), \ decltype(*(std::declval < T > ().begin())) > \\ ::declval < T > ().begin())) > \\$

Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

The documentation for this struct was generated from the following file:


· traits.h

7.29 qpp::is_matrix_expression < Derived > Struct Template Reference


Checks whether the type is an Eigen matrix expression.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_matrix_expression< Derived >:



Collaboration diagram for qpp::is_matrix_expression< Derived >:



7.29.1 Detailed Description

template < typename Derived > struct qpp::is_matrix_expression < Derived >

Checks whether the type is an Eigen matrix expression.

Provides the constant member *value* which is equal to *true*, if the type is an Eigen matrix expression of type *Eigen* :: *MatrixBase* < *Derived* >. Otherwise, *value* is equal to *false*.


The documentation for this struct was generated from the following file:

7.30 qpp::QCircuit::iterator Class Reference

Quantum circuit bound-checking (safe) iterator.

#include <classes/circuits.h>

Collaboration diagram for qpp::QCircuit::iterator:



Classes

class value_type_

Public Types

• using difference_type = long long

iterator trait

using value_type = value_type_

iterator trait

• using pointer = const value_type *

iterator trait

• using reference = const value_type &

iterator trait

• using iterator_category = std::forward_iterator_tag

iterator trait

Public Member Functions

• iterator ()=default

Default constructor.

• iterator (const iterator &)=default

Default copy constructor.

iterator & operator= (const iterator &)=default

Default copy assignment operator.

• iterator & operator++ ()

Prefix increment operator.

iterator operator++ (int)

Postfix increment operator.

• bool operator== (const iterator &rhs) const

Equality operator.

```
    bool operator!= (iterator rhs) const
Inequality operator.
```

• const value_type_ & operator* () const

Safe de-referencing operator.

void set_begin_ (const QCircuit *qc)

Sets the iterator to std::begin(this)

void set_end_ (const QCircuit *qc)

Sets the iterator to std::begin(this)

Private Attributes

```
    const QCircuit * qc_ {nullptr}
    < non-owning pointer to const quantum circuit</li>
```

value_type_ elem_ {nullptr}

7.30.1 Detailed Description

Quantum circuit bound-checking (safe) iterator.

Note

The iterator is a const_iterator by default

7.30.2 Member Typedef Documentation

```
7.30.2.1 difference_type
```

```
using qpp::QCircuit::iterator::difference_type = long long
```

iterator trait

7.30.2.2 iterator_category

```
using qpp::QCircuit::iterator::iterator_category = std::forward_iterator_tag
```

iterator trait

```
7.30.2.3 pointer
using qpp::QCircuit::iterator::pointer = const value_type*
iterator trait
7.30.2.4 reference
using qpp::QCircuit::iterator::reference = const value_type&
iterator trait
7.30.2.5 value_type
using qpp::QCircuit::iterator::value_type = value_type_
iterator trait
7.30.3 Constructor & Destructor Documentation
7.30.3.1 iterator() [1/2]
qpp::QCircuit::iterator::iterator ( ) [default]
Default constructor.
7.30.3.2 iterator() [2/2]
qpp::QCircuit::iterator::iterator (
             const iterator & ) [default]
Default copy constructor.
7.30.4 Member Function Documentation
7.30.4.1 operator"!=()
bool qpp::QCircuit::iterator::operator!= (
             iterator rhs ) const [inline]
```

Inequality operator.

Parameters

rhs | Iterator against which the inequality is being tested

Returns

True if the iterators are not equal (bit by bit), false otherwise

```
7.30.4.2 operator*()
```

```
const value_type_& qpp::QCircuit::iterator::operator* ( ) const [inline]
```

Safe de-referencing operator.

Returns

Constant reference to the iterator element

```
7.30.4.3 operator++() [1/2]
```

```
iterator& qpp::QCircuit::iterator::operator++ ( ) [inline]
```

Prefix increment operator.

Returns

Reference to the current instance

```
7.30.4.4 operator++() [2/2]
```

Postfix increment operator.

Returns

Copy of the current instance before the increment

```
7.30.4.5 operator=()
```

Default copy assignment operator.

Returns

Reference to the current instance

```
7.30.4.6 operator==()
```

Equality operator.

Parameters

rhs | Iterator against which the equality is being tested

Returns

True if the iterators are equal, false otherwise

```
7.30.4.7 set_begin_()
```

Sets the iterator to std::begin(this)

Parameters

qc | Pointer to constant quantum circuit

```
7.30.4.8 set_end_()
```

Sets the iterator to std::begin(this)

Parameters

qc Pointer to constant quantum circuit

7.30.5 Member Data Documentation

```
7.30.5.1 elem_
value_type_ qpp::QCircuit::iterator::elem_ {nullptr} [private]

7.30.5.2 qc_
const QCircuit* qpp::QCircuit::iterator::qc_ {nullptr} [private]
```

The documentation for this class was generated from the following file:

· classes/circuits.h

7.31 qpp::internal::KeyEqualEigen Class Reference

Functor for comparing Eigen expressions.

< non-owning pointer to const quantum circuit

```
#include <functions.h>
```

Public Member Functions

template<typename Derived >
 bool operator() (const Eigen::MatrixBase< Derived > &A, const Eigen::MatrixBase< Derived > &B) const

7.31.1 Detailed Description

Functor for comparing Eigen expressions.

Note

Works without assertion fails even if the dimensions of the arguments are different (in which case simply returns false

7.31.2 Member Function Documentation

7.31.2.1 operator()()

The documentation for this class was generated from the following file:

· functions.h

7.32 qpp::make_void < Ts > Struct Template Reference

```
Helper for <a href="mailto:qpp::to_void">qpp::to_void<>> alias template.</a>
```

```
#include <traits.h>
```

Public Types

· typedef void type

7.32.1 Detailed Description

```
template<typename... Ts>
struct qpp::make_void< Ts>
```

Helper for qpp::to_void<>> alias template.

See also

```
qpp::to_void<>
```

7.32.2 Member Typedef Documentation

```
7.32.2.1 type
```

```
template<typename... Ts>
typedef void qpp::make_void< Ts >::type
```

The documentation for this struct was generated from the following file:


traits.h

7.33 qpp::exception::MatrixMismatchSubsys Class Reference


Matrix mismatch subsystems exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixMismatchSubsys:



Collaboration diagram for qpp::exception::MatrixMismatchSubsys:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.33.1 Detailed Description

Matrix mismatch subsystems exception.

Matrix size mismatch subsystem sizes (e.g. in qpp::apply())

7.33.2 Member Function Documentation

7.33.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.33.2.2 type_description()

```
std::string qpp::exception::MatrixMismatchSubsys::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.34 qpp::exception::MatrixNotCvector Class Reference


Matrix is not a column vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotCvector:



Collaboration diagram for qpp::exception::MatrixNotCvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.34.1 Detailed Description

Matrix is not a column vector exception.

Eigen::Matrix is not a column vector

7.34.2 Member Function Documentation

7.34.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.34.2.2 type_description()

std::string qpp::exception::MatrixNotCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.35 qpp::exception::MatrixNotRvector Class Reference


Matrix is not a row vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotRvector:



Collaboration diagram for qpp::exception::MatrixNotRvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.35.1 Detailed Description

Matrix is not a row vector exception.

Eigen::Matrix is not a row vector

7.35.2 Member Function Documentation

7.35.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.35.2.2 type_description()

std::string qpp::exception::MatrixNotRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.36 qpp::exception::MatrixNotSquare Class Reference


Matrix is not square exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquare:



Collaboration diagram for qpp::exception::MatrixNotSquare:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.36.1 Detailed Description

Matrix is not square exception.

Eigen::Matrix is not a square matrix

7.36.2 Member Function Documentation

7.36.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.36.2.2 type_description()

std::string qpp::exception::MatrixNotSquare::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.37 qpp::exception::MatrixNotSquareNorCvector Class Reference


Matrix is not square nor column vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorCvector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorCvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.37.1 Detailed Description

Matrix is not square nor column vector exception.

Eigen::Matrix is not a square matrix nor a column vector

7.37.2 Member Function Documentation

7.37.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.37.2.2 type_description()

```
std::string qpp::exception::MatrixNotSquareNorCvector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.38 qpp::exception::MatrixNotSquareNorRvector Class Reference


Matrix is not square nor row vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorRvector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorRvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.38.1 Detailed Description

Matrix is not square nor row vector exception.

Eigen::Matrix is not a square matrix nor a row vector

7.38.2 Member Function Documentation

7.38.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.38.2.2 type_description()

```
std::string qpp::exception::MatrixNotSquareNorRvector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.39 qpp::exception::MatrixNotSquareNorVector Class Reference


Matrix is not square nor vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorVector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorVector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.39.1 Detailed Description

Matrix is not square nor vector exception.

Eigen::Matrix is not a square matrix nor a row/column vector

7.39.2 Member Function Documentation

7.39.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.39.2.2 type_description()

```
std::string qpp::exception::MatrixNotSquareNorVector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.40 qpp::exception::MatrixNotVector Class Reference


Matrix is not a vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotVector:



Collaboration diagram for qpp::exception::MatrixNotVector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.40.1 Detailed Description

Matrix is not a vector exception.

Eigen::Matrix is not a row or column vector

7.40.2 Member Function Documentation

7.40.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.40.2.2 type_description()

std::string qpp::exception::MatrixNotVector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.41 qpp::QCircuit::MeasureStep Struct Reference

One step consisting only of measurements in the circuit.

#include <classes/circuits.h>

Collaboration diagram for qpp::QCircuit::MeasureStep:



Public Member Functions

• MeasureStep ()=default

Default constructor.

MeasureStep (MeasureType measurement_type, const std::vector < cmat > &mats, const std::vector < idx > &target, idx c reg, std::string name="")

Constructs a measurement step instance.

Public Attributes

• MeasureType measurement_type_ = MeasureType::NONE

measurement type

- std::vector< cmat > mats
- std::vector < idx > target_

target where the measurement is applied

- idx c_reg_ {}
- std::string name_

custom name of the step

7.41.1 Detailed Description

One step consisting only of measurements in the circuit.

7.41.2 Constructor & Destructor Documentation

```
7.41.2.1 MeasureStep() [1/2]

qpp::QCircuit::MeasureStep::MeasureStep ( ) [default]
```

7.41.2.2 MeasureStep() [2/2]

Default constructor.

Constructs a measurement step instance.

Parameters

measurement_type	Measurement type
mats	Vector of measurement matrices (can be only one or many for Kraus measurements)
target	Target qudit indexes
c_reg	Classical register where the value of the measurement is stored
step_no	Circuit step number
name	Optional gate name

7.41.3 Member Data Documentation

```
7.41.3.1 c_reg_
idx qpp::QCircuit::MeasureStep::c_reg_ {}
```

matrix/matrices that specify the measurement

index of the classical register where the measurement result is being stored

```
7.41.3.2 mats_
std::vector<cmat> qpp::QCircuit::MeasureStep::mats_
```

7.41.3.3 measurement_type_

```
MeasureType qpp::QCircuit::MeasureStep::measurement_type_ = MeasureType::NONE
```

measurement type

7.41.3.4 name_

```
std::string qpp::QCircuit::MeasureStep::name_
```

custom name of the step

7.41.3.5 target_

```
std::vector<idx> qpp::QCircuit::MeasureStep::target_
```

target where the measurement is applied

The documentation for this struct was generated from the following file:


· classes/circuits.h

7.42 qpp::exception::NoCodeword Class Reference


Codeword does not exist exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::NoCodeword:



Collaboration diagram for qpp::exception::NoCodeword:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.42.1 Detailed Description

Codeword does not exist exception.

Codeword does not exist, thrown when calling qpp::Codes::codeword() with an invalid index

7.42.2 Member Function Documentation

7.42.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.42.2.2 type_description()

```
std::string qpp::exception::NoCodeword::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.43 qpp::NoiseBase < T > Class Template Reference

Base class for all noise models, derive your particular noise model.

```
#include <classes/noise.h>
```

Collaboration diagram for qpp::NoiseBase< T >:



Public Types

• using noise_type = T

Public Member Functions

• template<typename U = noise_type>

NoiseBase (const std::vector< cmat > &Ks, typename std::enable_if< std::is_same< NoiseType::StateDependent, U >::value >::type *=nullptr)

Constructs a noise instance for StateDependent noise type.

• template<typename U = noise_type>

NoiseBase (const std::vector< cmat > &Ks, const std::vector< double > &probs, typename std::enable_if< std::is same< NoiseType::StateIndependent, U >::value >::type *=nullptr)

Constructs a noise instance for StateIndependent noise type.

virtual ∼NoiseBase ()=default

Default virtual destructor.

idx get_d () const noexcept

Qudit dimension.

std::vector< cmat > get_Ks () const

Vector of noise operators.

std::vector< double > get_probs () const

Vector of probabilities corresponding to each noise operator.

• idx get last idx () const

Index of the last occurring noise element.

double get_last_p () const

Probability of the last occurring noise element.

cmat get_last_K () const

Last occurring noise element.

· virtual cmat operator() (const cmat &state, idx target) const

Function invocation operator, applies the underlying noise model on qudit target of the multi-partite state vector or density matrix state.

virtual cmat operator() (const cmat &state, const std::vector < idx > &target) const

Function invocation operator, applies the underlying correlated noise model on qudits specified by target of the multipartite state vector or density matrix state.

Protected Member Functions

void compute_probs_ (const cmat &state, const std::vector < idx > &target) const
 Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

• cmat compute state (const cmat &state, const std::vector < idx > &target) const

Compute the resulting state after the noise was applied.

Protected Attributes

const std::vector< cmat > Ks

Kraus operators.

std::vector< double > probs_

probabilities

• idx d_ {}

qudit dimension

idx i_{}

index of the last occurring noise element

bool generated_ {false}

invoked, or if the noise is state-independent

7.43.1 Detailed Description

```
\label{eq:template} \begin{split} \text{template} &< \text{class T}> \\ \text{class qpp::NoiseBase} &< \text{T}> \end{split}
```

Base class for all noise models, derive your particular noise model.

7.43.2 Member Typedef Documentation

7.43.2.1 noise_type

```
template<class T>
using qpp::NoiseBase< T >::noise_type = T
```

7.43.3 Constructor & Destructor Documentation

7.43.3.1 NoiseBase() [1/2]

Constructs a noise instance for StateDependent noise type.

Note

SFINAEd-out for StateIndependent noise

Parameters

Α	Eigen expression (state vector or density matrix)
Ks	Vector of noise (Kraus) operators that specify the noise
d	Subsystem dimension

7.43.3.2 NoiseBase() [2/2]

template<class T>

Constructs a noise instance for StateIndependent noise type.

Note

SFINAEd-out for StateDependent noise

Parameters

Α	Eigen expression (state vector or density matrix)
Ks	Vector of noise (Kraus) operators that specify the noise
d	Subsystem dimension

7.43.3.3 ∼NoiseBase()

```
template<class T>
virtual qpp::NoiseBase< T >::~NoiseBase ( ) [virtual], [default]
```

Default virtual destructor.

7.43.4 Member Function Documentation

7.43.4.1 compute_probs_()

Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

Parameters

state	State vector or density matrix
target	Qudit indexes where the noise is applied

7.43.4.2 compute_state_()

Compute the resulting state after the noise was applied.

Parameters

state	State vector or density matrix
target	Qudit indexes where the noise is applied

Returns

Resulting state after the noise was applied

7.43.4.3 get_d()

```
template<class T>
idx qpp::NoiseBase< T >::get_d ( ) const [inline], [noexcept]
```

Qudit dimension.

Returns

Qudit dimension

7.43.4.4 get_Ks()

```
template<class T>
std::vector<cmat> qpp::NoiseBase< T >::get_Ks () const [inline]
```

Vector of noise operators.

Returns

Vector of noise operators

```
7.43.4.5 get_last_idx()
```

```
template<class T>
idx qpp::NoiseBase< T >::get_last_idx ( ) const [inline]
```

Index of the last occurring noise element.

Returns

Index of the last occurring noise element

```
7.43.4.6 get_last_K()
```

```
template<class T>
cmat qpp::NoiseBase< T >::get_last_K ( ) const [inline]
```

Last occurring noise element.

Returns

Last occurring noise element

```
7.43.4.7 get_last_p()
```

```
template<class T>
double qpp::NoiseBase< T >::get_last_p ( ) const [inline]
```

Probability of the last occurring noise element.

Returns

Probability of the last occurring noise element

```
7.43.4.8 get_probs()
```

```
template<class T>
std::vector<double> qpp::NoiseBase< T >::get_probs ( ) const [inline]
```

Vector of probabilities corresponding to each noise operator.

Returns

Probability vector

```
7.43.4.9 operator()() [1/2]
```

Function invocation operator, applies the underlying noise model on qudit *target* of the multi-partite state vector or density matrix *state*.

Parameters

state	Multi-partite state vector or density matrix
target	Qudit index where the noise is applied

Returns

Resulting state vector or density matrix

7.43.4.10 operator()() [2/2]

Function invocation operator, applies the underlying correlated noise model on qudits specified by *target* of the multi-partite state vector or density matrix *state*.

Parameters

state	Multi-partite state vector or density matrix
target	Qudit indexes where the correlated noise is applied

Returns

Resulting state vector or density matrix

7.43.5 Member Data Documentation

7.43.5.1 d_

```
template<class T>
idx qpp::NoiseBase< T >::d_ {} [mutable], [protected]
qudit dimension
```

7.43.5.2 generated_

```
template<class T>
bool qpp::NoiseBase< T >::generated_ {false} [mutable], [protected]
```

invoked, or if the noise is state-independent

set to true after compute_state_() is

7.43.5.3 i_

```
template<class T>
idx qpp::NoiseBase< T >::i_ {} [mutable], [protected]
```

index of the last occurring noise element

7.43.5.4 Ks_

```
template<class T>
const std::vector<cmat> qpp::NoiseBase< T >::Ks_ [protected]
```

Kraus operators.

7.43.5.5 probs

```
template<class T>
std::vector<double> qpp::NoiseBase< T >::probs_ [mutable], [protected]
```

probabilities

The documentation for this class was generated from the following file:

• classes/noise.h

7.44 qpp::NoiseType Class Reference

Contains template tags used to specify the noise type.

```
#include <classes/noise.h>
```

Classes

class StateDependent

Template tag, used whenever the noise is state-dependent.

· class StateIndependent

Template tag, used whenever the noise is state-independent.

7.44.1 Detailed Description

Contains template tags used to specify the noise type.

The documentation for this class was generated from the following file:


• classes/noise.h

7.45 qpp::exception::NotBipartite Class Reference


Not bi-partite exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotBipartite:



Collaboration diagram for qpp::exception::NotBipartite:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.45.1 Detailed Description

Not bi-partite exception.

std::vector<idx> of dimensions has size different from 2

7.45.2 Member Function Documentation

7.45.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.45.2.2 type_description()

```
std::string qpp::exception::NotBipartite::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.46 qpp::exception::NotImplemented Class Reference


Code not yet implemented.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotImplemented:



Collaboration diagram for qpp::exception::NotImplemented:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.46.1 Detailed Description

Code not yet implemented.

7.46.2 Member Function Documentation

7.46.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.46.2.2 type_description()

```
std::string qpp::exception::NotImplemented::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.47 qpp::exception::NotQubitCvector Class Reference


Column vector is not 2 x 1 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitCvector:



Collaboration diagram for qpp::exception::NotQubitCvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.47.1 Detailed Description

Column vector is not 2 x 1 exception.

Eigen::Matrix is not 2 x 1

7.47.2 Member Function Documentation

7.47.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.47.2.2 type_description()

std::string qpp::exception::NotQubitCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.48 qpp::exception::NotQubitMatrix Class Reference


Matrix is not 2 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitMatrix:



Collaboration diagram for qpp::exception::NotQubitMatrix:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.48.1 Detailed Description

Matrix is not 2 x 2 exception.

Eigen::Matrix is not 2 x 2

7.48.2 Member Function Documentation

7.48.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.48.2.2 type_description()

std::string qpp::exception::NotQubitMatrix::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.49 qpp::exception::NotQubitRvector Class Reference


Row vector is not 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitRvector:



Collaboration diagram for qpp::exception::NotQubitRvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.49.1 Detailed Description

Row vector is not 1 x 2 exception.

Eigen::Matrix is not 1 x 2

7.49.2 Member Function Documentation

7.49.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.49.2.2 type_description()

std::string qpp::exception::NotQubitRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.50 qpp::exception::NotQubitSubsys Class Reference


Subsystems are not qubits exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitSubsys:



Collaboration diagram for qpp::exception::NotQubitSubsys:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.50.1 Detailed Description

Subsystems are not qubits exception.

Subsystems are not 2-dimensional (qubits)

7.50.2 Member Function Documentation

7.50.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

7.50.2.2 type_description()

```
std::string qpp::exception::NotQubitSubsys::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.51 qpp::exception::NotQubitVector Class Reference


Vector is not 2 x 1 nor 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitVector:



Collaboration diagram for qpp::exception::NotQubitVector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.51.1 Detailed Description

Vector is not 2 x 1 nor 1 x 2 exception.

Eigen::Matrix is not 2 x 1 nor 1 x 2

7.51.2 Member Function Documentation

7.51.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.51.2.2 type_description()

std::string qpp::exception::NotQubitVector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.52 qpp::exception::OutOfRange Class Reference


Argument out of range exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::OutOfRange:



Collaboration diagram for qpp::exception::OutOfRange:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.52.1 Detailed Description

Argument out of range exception.

Argument out of range

7.52.2 Member Function Documentation

7.52.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.52.2.2 type_description()

```
std::string qpp::exception::OutOfRange::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.53 qpp::exception::PermInvalid Class Reference


Invalid permutation exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermInvalid:



Collaboration diagram for qpp::exception::PermInvalid:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.53.1 Detailed Description

Invalid permutation exception.

std::vector<idx> does note represent a valid permutation

7.53.2 Member Function Documentation

7.53.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.53.2.2 type_description()

std::string qpp::exception::PermInvalid::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.54 qpp::exception::PermMismatchDims Class Reference


Permutation mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermMismatchDims:



Collaboration diagram for qpp::exception::PermMismatchDims:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.54.1 Detailed Description

Permutation mismatch dimensions exception.

Size of the std::vector<idx> representing the permutation is different from the size of the std::vector<idx> of dimensions

7.54.2 Member Function Documentation

7.54.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception

7.54.2.2 type_description()

```
std::string qpp::exception::PermMismatchDims::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.55 qpp::QCircuit Class Reference


Quantum circuit class.

#include <classes/circuits.h>

Inheritance diagram for qpp::QCircuit:



Collaboration diagram for qpp::QCircuit:



Classes

struct GateStep

One step consisting only of gates/operators in the circuit.

· class iterator

Quantum circuit bound-checking (safe) iterator.

struct MeasureStep

One step consisting only of measurements in the circuit.

Public Types

enum GateType {
 GateType::NONE, GateType::SINGLE, GateType::TWO, GateType::THREE,
 GateType::CUSTOM, GateType::FAN, GateType::QFT, GateType::TFQ,
 GateType::SINGLE_CTRL_SINGLE_TARGET, GateType::SINGLE_CTRL_MULTIPLE_TARGET, GateType::MULTIPLE_CTR

GateType::MULTIPLE_CTRL_MULTIPLE_TARGET,

GateType::CUSTOM_CTRL, GateType::SINGLE_cCTRL_SINGLE_TARGET, GateType::SINGLE_cCTRL_MULTIPLE_TARGE GateType::MULTIPLE cCTRL SINGLE TARGET,

GateType::MULTIPLE_cCTRL_MULTIPLE_TARGET, GateType::CUSTOM_cCTRL }

Type of gate being executed in a gate step.

 enum MeasureType { MeasureType::NONE, MeasureType::MEASURE_Z, MeasureType::MEASURE_V, MeasureType::MEASURE_V_MANY }

Type of measurement being executed in a measurement step.

enum StepType { StepType::NONE, StepType::GATE, StepType::MEASUREMENT }

Types of each step in the quantum circuit.

· using const iterator = iterator

both iterators are const_iterators

Public Member Functions

· iterator begin ()

Iterator to the first element.

· const iterator begin () const noexcept

Constant iterator to the first element.

· const iterator cbegin () const noexcept

Constant iterator to the first element.

• iterator end ()

Iterator to the next to the last element.

const_iterator end () const noexcept

Constant iterator to the next to the last element.

· const iterator cend () const noexcept

Constant iterator to the next to the last element.

QCircuit (idx nq, idx nc=0, idx d=2, std::string name="")

Constructs a quantum circuit.

virtual ~QCircuit ()=default

Default virtual destructor.

• idx get_nq () const noexcept

Total number of qudits in the circuit.

• idx get_nc () const noexcept

Total number of classical dits in the circuit.

• idx get_d () const noexcept

Dimension of the comprising qudits.

• std::string get_name () const

Quantum circuit name.

· idx get measured (idx i) const

Check whether qudit i was already measured.

std::vector< idx > get measured () const

Vector of already measured qudit indexes.

std::vector< idx > get_non_measured () const

Vector of non-measured qudit indexes.

idx get_gate_count () const noexcept

Quantum circuit total gate count.

idx get gate count (const std::string &name) const

Quantum circuit gate count.

idx get_gate_depth () const

Quantum circuit total gate depth.

• idx get_gate_depth (const std::string &name QPP_UNUSED_) const

Quantum circuit gate depth.

idx get_measurement_count () const noexcept

Quantum circuit total measurement count.

• idx get measurement count (const std::string &name) const

Quantum circuit measurement count.

• idx get_step_count () const noexcept

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

QCircuit & gate (const cmat &U, idx i, std::string name="")

Applies the single qudit gate U on single qudit i.

QCircuit & gate (const cmat &U, idx i, idx j, std::string name="")

Applies the two qudit gate U on qudits i and j.

QCircuit & gate (const cmat &U, idx i, idx j, idx k, std::string name="")

Applies the three qudit gate U on qudits i, j and k.

QCircuit & gate_fan (const cmat &U, const std::vector< idx > &target, std::string name="")

Applies the single qudit gate U on every qudit listed in target.

• QCircuit & gate_fan (const cmat &U, const std::initializer_list< idx > &target, std::string name="")

Applies the single qudit gate U on every qudit listed in target.

QCircuit & gate fan (const cmat &U, std::string name="")

Applies the single qudit gate U on every remaining non-measured qudit.

• QCircuit & gate_custom (const cmat &U, const std::vector < idx > &target, std::string name="")

Jointly applies the custom multiple qudit gate U on the qudit indexes specified by target.

QCircuit & QFT (const std::vector < idx > &target, bool swap QPP_UNUSED_=true)

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & TFQ (const std::vector < idx > &target, bool swap QPP_UNUSED_=true)

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & CTRL (const cmat &U, idx ctrl, idx target, std::string name="")

Applies the single qudit controlled gate U with control qudit ctrl and target qudit target.

QCircuit & CTRL (const cmat &U, idx ctrl, const std::vector < idx > &target, std::string name="")

Applies the single qudit controlled gate U with control qudit ctrl on every qudit listed in target.

QCircuit & CTRL (const cmat &U, const std::vector< idx > &ctrl, idx target, std::string name="")

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on the target qudit target.

QCircuit & CTRL (const cmat &U, const std::vector < idx > &ctrl, const std::vector < idx > &target, std::string name="")

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on every qudit listed in target.

QCircuit & CTRL_custom (const cmat &U, const std::vector < idx > &ctrl, const std::vector < idx > &target, std::string name="")

Jointly applies the custom multiple-qudit controlled gate U with multiple control qudits listed in ctrl on the qudit indexes specified by target.

• QCircuit & cCTRL (const cmat &U, idx ctrl dit, idx target, std::string name="")

Applies the single qubit controlled gate U with classical control dit ctrl and target qudit target.

QCircuit & cCTRL (const cmat &U, idx ctrl_dit, const std::vector < idx > &target, std::string name="")

Applies the single qudit controlled gate U with classical control dit ctrl on every qudit listed in target.

QCircuit & cCTRL (const cmat &U, const std::vector < idx > &ctrl dits, idx target, std::string name="")

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on the target qudit target.

QCircuit & cCTRL (const cmat &U, const std::vector< idx > &ctrl_dits, const std::vector< idx > &target, std::string name="")

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on every qudit listed in target.

QCircuit & cCTRL_custom (const cmat &U, const std::vector< idx > &ctrl_dits, const std::vector< idx > &target, std::string name="")

Jointly applies the custom multiple-qudit controlled gate U with multiple classical control dits listed in ctrl on the qudit indexes specified by target.

QCircuit & measureZ (idx target, idx c_reg, std::string name="")

Measurement of single qudit in the computational basis (Z-basis)

QCircuit & measureV (const cmat &V, idx target, idx c_reg, std::string name="")

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

QCircuit & measureV (const cmat &V, const std::vector< idx > &target, idx c_reg, std::string name="")

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix ν

std::string to_JSON (bool enclosed_in_curly_brackets=true) const override
 qpp::/JOSN::to_JSON() override

Private Member Functions

- const std::vector< MeasureStep > & get_measurements_ () const noexcept
 - Vector of qpp::QCircuit::MeasureStep.
- const std::vector< GateStep > & get_gates_ () const noexcept

Vector of qpp::QCircuit::GateStep.

std::ostream & display (std::ostream &os) const override

qpp::IDisplay::display() override

Private Attributes

```
    const idx nq_
```

number of audits

const idx nc

number of classical "dits"

const idx d

qudit dimension

• std::string name_

optional circuit name

• std::vector< bool > measured_

keeps track of the measured qudits

std::unordered_map< std::string, idx > depth_{{}}

keeps track of the gate depths

• std::unordered map< std::string, idx > count {}

keeps track of the gate counts

std::unordered_map< std::string, idx > measurement_count_{}{}

keeps track of the measurement counts

std::vector< GateStep > gates_{}{}

gates

std::vector< MeasureStep > measurements_{}{}

measurements

std::vector< StepType > step_types_{}

type of each step

Friends

- class QEngine
- std::ostream & operator<< (std::ostream &os, const GateType &gate_type)

Extraction operator overload for qpp::QCircuit::GateType enum class.

• std::ostream & operator<< (std::ostream &os, const GateStep &gate_step)

Extraction operator overload for qpp::QCircuit::GateStep class.

std::ostream & operator<< (std::ostream &os, const MeasureType &measure_type)

Extraction operator overload for qpp::QCircuit::MeasureType enum class.

std::ostream & operator<< (std::ostream &os, const MeasureStep &measure_step)

Extraction operator overload for qpp::QCircuit::MeasureStep class.

7.55.1 Detailed Description

Quantum circuit class.

See also

qpp::QEngine

7.55.2 Member Typedef Documentation

7.55.2.1 const_iterator

```
using qpp::QCircuit::const_iterator = iterator
```

both iterators are const_iterators

7.55.3 Member Enumeration Documentation

7.55.3.1 GateType

```
enum qpp::QCircuit::GateType [strong]
```

Type of gate being executed in a gate step.

Enumerator

NONE	represents no gate
SINGLE	unitary gate on a single qudit
TWO	unitary gate on 2 qudits
THREE	unitary gate on 3 qudits
CUSTOM	custom gate on multiple qudits

Enumerator

FAN	same unitary gate on multiple qudits
QFT	quantum Fourier transform,
TFQ	quantum inverse Fourier transform,
SINGLE_CTRL_SINGLE_TARGET	one control and one target controlled 1 qudit unitary gate with
SINGLE_CTRL_MULTIPLE_TARGET	one control and multiple targets controlled 1 qudit unitary gate with
MULTIPLE_CTRL_SINGLE_TARGET	multiple controls and single target controlled 1 qudit unitary gate with
MULTIPLE_CTRL_MULTIPLE_TARGET	multiple controls and multiple targets controlled 1 qudit unitary gate with
CUSTOM_CTRL	and multiple targets custom controlled gate with multiple controls
SINGLE_cCTRL_SINGLE_TARGET	one classical control and one target controlled 1 qudit unitary gate with
SINGLE_cCTRL_MULTIPLE_TARGET	one classical control and multiple targets controlled 1 qudit unitary gate with
MULTIPLE_cCTRL_SINGLE_TARGET	multiple classical controls and single target controlled 1 qudit unitary gate with
MULTIPLE_cCTRL_MULTIPLE_TARGET	with multiple classical controls and multiple targets controlled 1 qudit unitary gate
CUSTOM_cCTRL	multiple targets custom controlled gate with multiple controls and

7.55.3.2 MeasureType

```
enum qpp::QCircuit::MeasureType [strong]
```

Type of measurement being executed in a measurement step.

Enumerator

NONE	represents no measurement
MEASURE_Z	Z measurement of single qudit.
MEASURE_V	or rank-1 projectors specified by the columns of matrix V measurement of single qudit in the orthonormal basis
MEASURE_V_MANY	basis or rank-1 projectors specified by the columns of matrix \it{V} measurement of multiple qudits in the orthonormal

7.55.3.3 StepType

```
enum qpp::QCircuit::StepType [strong]
```

Types of each step in the quantum circuit.

Enumerator

NONE	represents no step
GATE	quantum gate
MEASUREMENT	measurement

7.55.4 Constructor & Destructor Documentation

7.55.4.1 QCircuit()

```
qpp::QCircuit::QCircuit (
    idx nq,
    idx nc = 0,
    idx d = 2,
    std::string name = "" ) [inline], [explicit]
```

Constructs a quantum circuit.

Note

The measurement results can only be stored in the classical dits of which number is specified by nc

Parameters

nq	Number of qbits	
nc	Number of classical dits	
d	Subsystem dimensions (optional, default is qubit, i.e. $d = 2$)	
name	Circuit name (optional)	

7.55.4.2 ~QCircuit()

```
virtual qpp::QCircuit::~QCircuit ( ) [virtual], [default]
```

Default virtual destructor.

7.55.5 Member Function Documentation

```
7.55.5.1 begin() [1/2]
```

```
iterator qpp::QCircuit::begin ( ) [inline]
```

Iterator to the first element.

Returns

Iterator to the first element

```
7.55.5.2 begin() [2/2]
const_iterator qpp::QCircuit::begin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

7.55.5.3 cbegin()

```
const_iterator qpp::QCircuit::cbegin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

Applies the single qubit controlled gate *U* with classical control dit *ctrl* and target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit index
name	Optional gate name

Generated by Doxygen

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with classical control dit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the
	classical control dits
name	Optional gate name

Returns

Reference to the current instance

```
7.55.5.6 cCTRL() [3/4]
```

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

7.55.5.7 cCTRL() [4/4]

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the
	classical control dits
name	Optional gate name

Returns

Reference to the current instance

7.55.5.8 cCTRL_custom()

Jointly applies the custom multiple-qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the qudit indexes specified by *target*.

Parameters

U	Multiple-qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit indexes where the gate U is applied depending on the values of the classical control dits
name	Optional gate name

Returns

Reference to the current instance

7.55.5.9 cend()

```
const_iterator qpp::QCircuit::cend ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

Returns

Constant iterator to the next to the last element

Applies the single qudit controlled gate *U* with control qudit *ctrl* and target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with control qudit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the control qudits
Genganen b	y Opption al gate name

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.55.5.13 CTRL() [4/4]
```

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

7.55.5.14 CTRL_custom()

Jointly applies the custom multiple-qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the qudit indexes specified by *target*.

Parameters

U	Multiple-qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes where the gate U is applied depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

7.55.5.15 display()

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the quantum circuit

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.55.5.16 end() [1/2]
```

```
iterator qpp::QCircuit::end ( ) [inline]
```

Iterator to the next to the last element.

Returns

Iterator to the next to the last element

```
7.55.5.17 end() [2/2]
const_iterator qpp::QCircuit::end ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

Returns

Constant iterator to the next to the last element

Applies the single qudit gate *U* on single qudit *i*.

Parameters

U	Single qudit quantum gate
i	Qudit index
name	Optional gate name

Returns

Reference to the current instance

```
idx i,
idx j,
std::string name = "" ) [inline]
```

Applies the two qudit gate U on qudits i and j.

Parameters

U	Two qudit quantum gate
i	Qudit index
j	Qudit index
name	Optional gate name

Returns

Reference to the current instance

std::string name = "") [inline]

Applies the three qudit gate U on qudits i, j and k.

Parameters

U	Three qudit quantum gate
i	Qudit index
j	Qudit index
k	Qudit index
name	Optional gate name

idx k,

Returns

Reference to the current instance

7.55.5.21 gate_custom()

Jointly applies the custom multiple qudit gate *U* on the qudit indexes specified by *target*.

Parameters

U	Multiple qudit quantum gate
target	Subsystem indexes where the gate U is applied
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit gate *U* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
target	Target qudit indexes; the gate U is applied on every one of them
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit gate U on every qudit listed in target.

Parameters

U	Single qudit quantum gate
target	Target qudit indexes; the gate U is applied on every one of them
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit gate U on every remaining non-measured qudit.

Parameters

U	Single qudit quantum gate
name	Optional gate name

Returns

Reference to the current instance

```
7.55.5.25 get_d()
idx qpp::QCircuit::get_d ( ) const [inline], [noexcept]
```

Dimension of the comprising qudits.

Returns

Qudit dimension

```
7.55.5.26 get_gate_count() [1/2]
idx qpp::QCircuit::get_gate_count ( ) const [inline], [noexcept]
```

Quantum circuit total gate count.

Returns

Total gate count

Quantum circuit gate count.

Da			_ 1		
Pа	ra	m	eı	re	rs

```
name Gate name
```

Returns

Gate count

```
7.55.5.28 get_gate_depth() [1/2]
idx qpp::QCircuit::get_gate_depth ( ) const [inline]
```

Quantum circuit total gate depth.

Returns

Total gate depth

```
7.55.5.29 get_gate_depth() [2/2]
```

Quantum circuit gate depth.

Parameters

```
name Gate name
```

Returns

Gate depth

```
7.55.5.30 get_gates_()
```

```
\verb|const| std::vector < \verb|GateStep>& qpp::QCircuit::get_gates_ ( ) const [inline], [private], [noexcept]| \\
```

Vector of qpp::QCircuit::GateStep.

Returns

Vector of qpp::QCircuit::GateStep

```
7.55.5.31 get_measured() [1/2]
```

Check whether qudit *i* was already measured.

Parameters

```
i Qudit index
```

Returns

True if qudit i was already measured, false othwewise

```
7.55.5.32 get_measured() [2/2]
std::vector<idx> qpp::QCircuit::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

```
7.55.5.33 get_measurement_count() [1/2]
```

```
idx qpp::QCircuit::get_measurement_count ( ) const [inline], [noexcept]
```

Quantum circuit total measurement count.

Returns

Total measurement count

7.55.5.34 get_measurement_count() [2/2]

Quantum circuit measurement count.

Parameters

name Measurement name

Returns

Measurement count

7.55.5.35 get_measurements_()

```
const std::vector<MeasureStep>& qpp::QCircuit::get_measurements_ ( ) const [inline], [private],
[noexcept]
```

Vector of qpp::QCircuit::MeasureStep.

Returns

Vector of qpp::QCircuit::MeasureStep

7.55.5.36 get_name()

```
std::string qpp::QCircuit::get_name ( ) const [inline]
```

Quantum circuit name.

Returns

Quantum circuit name

7.55.5.37 get_nc()

```
idx qpp::QCircuit::get_nc ( ) const [inline], [noexcept]
```

Total number of classical dits in the circuit.

Returns

Total number of classical dits

7.55.5.38 get_non_measured()

```
std::vector<idx> qpp::QCircuit::get_non_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

Returns

Vector of non-measured qudit indexes

```
7.55.5.39 get_nq()
```

```
idx qpp::QCircuit::get_nq ( ) const [inline], [noexcept]
```

Total number of qudits in the circuit.

Returns

Total number of qudits

```
7.55.5.40 get_step_count()
```

```
idx qpp::QCircuit::get_step_count ( ) const [inline], [noexcept]
```

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

Returns

Total (gates + measurements) count

7.55.5.41 measureV() [1/2]

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V	
target	Qudit index	_
Generated b	eg Classical register where the value of the measurement is stored	
name	Optional measurement name	

Returns

Reference to the current instance

7.55.5.42 measureV() [2/2]

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V	
target	Target qudit indexes that are jointly measured	
c_reg	G Classical register where the value of the measurement is stored	
name	Optional measurement name	

Returns

Reference to the current instance

7.55.5.43 measureZ()

```
QCircuit& qpp::QCircuit::measureZ (
         idx target,
         idx c_reg,
         std::string name = "" ) [inline]
```

Measurement of single qudit in the computational basis (Z-basis)

Parameters

target	Qudit index
c_reg	Classical register where the value of the measurement is being stored
name	Optional measurement name, default is "Measure Z"

Returns

Reference to the current instance

7.55.5.44 QFT()

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

7.55.5.45 TFQ()

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the inverse quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

7.55.5.46 to_JSON()

qpp::IJOSN::to_JSON() override

Displays the quantum circuit in JSON format

Parameters

enclosed_in_curly_brackets	If true, encloses the result in curly brackets
----------------------------	--

Returns

String containing the JSON representation of the quantum circuit

Implements qpp::IJSON.

7.55.6 Friends And Related Function Documentation

Extraction operator overload for qpp::QCircuit::GateType enum class.

Parameters

os	Output stream
gate_type	qpp::QCircuit::GateType enum class

Returns

Output stream

```
7.55.6.2 operator<< [2/4]
std::ostream& operator<< (</pre>
```

std::ostream & os,

Extraction operator overload for qpp::QCircuit::GateStep class.

const GateStep & gate_step) [friend]

Parameters

os	Output stream
gate_type	qpp::QCircuit::GateStep class

Returns

Output stream

Extraction operator overload for qpp::QCircuit::MeasureType enum class.

Parameters

os	Output stream
gate_type	qpp::QCircuit::MeasureType enum class

Returns

Output stream

Extraction operator overload for qpp::QCircuit::MeasureStep class.

Parameters

os	Output stream
gate_type	qpp::QCircuit::MeasureStep enum class

Returns

Output stream

7.55.6.5 QEngine

```
friend class QEngine [friend]
```

7.55.7 Member Data Documentation

keeps track of the measured qudits

```
7.55.7.1 count_
std::unordered_map<std::string, idx> qpp::QCircuit::count_ {} [private]
keeps track of the gate counts
7.55.7.2 d_
const idx qpp::QCircuit::d_ [private]
qudit dimension
7.55.7.3 depth_
std::unordered_map<std::string, idx> qpp::QCircuit::depth_ {} [private]
keeps track of the gate depths
7.55.7.4 gates_
std::vector<GateStep> qpp::QCircuit::gates_ {} [private]
gates
7.55.7.5 measured_
std::vector<bool> qpp::QCircuit::measured_ [private]
```

```
7.55.7.6 measurement_count_
std::unordered_map<std::string, idx> qpp::QCircuit::measurement_count_ {} [private]
keeps track of the measurement counts
7.55.7.7 measurements
std::vector<MeasureStep> qpp::QCircuit::measurements_ {} [private]
measurements
7.55.7.8 name_
std::string qpp::QCircuit::name_ [private]
optional circuit name
7.55.7.9 nc_
const idx qpp::QCircuit::nc_ [private]
number of classical "dits"
7.55.7.10 nq_
const idx qpp::QCircuit::nq_ [private]
number of qudits
7.55.7.11 step_types_
std::vector<StepType> qpp::QCircuit::step_types_ {} [private]
type of each step
```

Generated by Doxygen

classes/circuits.h


The documentation for this class was generated from the following file:

qpp::QEngine Class Reference 7.56


Quantum circuit engine, executes qpp::QCircuit.

#include <classes/circuits.h>

Inheritance diagram for qpp::QEngine:



Collaboration diagram for qpp::QEngine:



Public Member Functions

• QEngine (const QCircuit &qc)

Constructs a quantum engine out of a quantum circuit.

• QEngine (const QEngine &)=default

Default copy constructor.

• QEngine & operator= (const QEngine &)=default

Default copy assignment operator.

• QEngine (QCircuit &&)=delete

Disables rvalue QCircuit.

virtual ~QEngine ()=default

Default virtual destructor.

• ket get_psi () const

Underlying quantum state.

ket & get_ref_psi ()

Reference to the underlying quantum state.

std::vector< idx > get_dits () const

Vector with the values of the underlying classical dits.

idx get_dit (idx i) const

Value of the classical dit at position i.

std::vector< double > get_probs () const

Vector of underlying measurement outcome probabilities.

bool get_measured (idx i) const

Check whether qudit i was already measured.

• std::vector< idx > get_measured () const

Vector of already measured qudit indexes.

std::vector< idx > get_not_measured () const

Vector of non-measured qudit indexes.

const QCircuit & get circuit () const noexcept

Quantum circuit.

• QEngine & set_dit (idx i, idx value)

Sets the classical dit at position i.

• void reset ()

Resets the engine.

void execute (const QCircuit::iterator::value type &elem)

Executes one step in the quantum circuit.

void execute (const QCircuit::iterator &it)

Executes one step in the quantum circuit.

std::string to_JSON (bool enclosed_in_curly_brackets=true) const override

qpp::IJOSN::to_JSON() override

Protected Member Functions

void set_measured_ (idx i)

Marks qudit i as measured then re-label accordingly the remaining non-measured qudits.

std::vector< idx > get_relative_pos_ (std::vector< idx > v)

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

Protected Attributes

const QCircuit * qc_

pointer to constant quantum circuit

ket psi_

state vector

std::vector< idx > dits_

classical dits

std::vector< double > probs

measurement probabilities

std::vector< idx > subsys_

Private Member Functions

std::ostream & display (std::ostream &os) const override

qpp::IDisplay::display() override

7.56.1 Detailed Description

Quantum circuit engine, executes qpp::QCircuit.

See also

qpp::QCircuit

7.56.2 Constructor & Destructor Documentation

Constructs a quantum engine out of a quantum circuit.

Note

The quantum circuit must be an Ivalue

See also

```
qpp::QEngine(QCircuit&&)
```

Note

The initial underlying quantum state is set to $|0\rangle^{\otimes n}$

Parameters

```
qc Quantum circuit
```

7.56.2.2 QEngine() [2/3]

Default copy constructor.

Disables rvalue QCircuit.

```
7.56.2.4 \sim QEngine()
```

```
virtual qpp::QEngine::~QEngine ( ) [virtual], [default]
```

Default virtual destructor.

7.56.3 Member Function Documentation

7.56.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the state of the engine

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.56.3.2 execute() [1/2]
```

Executes one step in the quantum circuit.

Parameters

elem Step to be executed

```
7.56.3.3 execute() [2/2]
```

Executes one step in the quantum circuit.

Parameters

it Iterator to the step to be executed

7.56.3.4 get_circuit()

```
const QCircuit& qpp::QEngine::get_circuit ( ) const [inline], [noexcept]
```

Quantum circuit.

Returns

Underlying quantum circuit

7.56.3.5 get_dit()

```
idx qpp::QEngine::get_dit (
        idx i ) const [inline]
```

Value of the classical dit at position i.

Parameters

i Classical dit index

Returns

Value of the classical dit at position i

```
7.56.3.6 get_dits()
```

```
std::vector<idx> qpp::QEngine::get_dits ( ) const [inline]
```

Vector with the values of the underlying classical dits.

Returns

Vector of underlying classical dits

```
7.56.3.7 get_measured() [1/2]
```

```
bool qpp::QEngine::get_measured ( \label{eq:decomposition} \begin{subarray}{ll} idx i \end{subarray} ) const \begin{subarray}{ll} (inline) \end{subarray}
```

Check whether qudit i was already measured.

Parameters

```
i Qudit index
```

Returns

True if qudit i was already measured, false othwewise

```
7.56.3.8 get_measured() [2/2]
```

```
std::vector<idx> qpp::QEngine::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

7.56.3.9 get_not_measured()

```
std::vector<idx> qpp::QEngine::get_not_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

Returns

Vector of non-measured qudit indexes

7.56.3.10 get_probs()

```
std::vector<double> qpp::QEngine::get_probs ( ) const [inline]
```

Vector of underlying measurement outcome probabilities.

Note

The probability vector has the same length as the vector of classical dits. If the measurement result is stored at the index c_reg , then the outcome probability is automatically stored at the same index c_reg in the probability vector.

Returns

Vector of underlying measurement outcome probabilities

```
7.56.3.11 get_psi()
```

```
ket qpp::QEngine::get_psi ( ) const [inline]
```

Underlying quantum state.

Returns

Underlying quantum state

```
7.56.3.12 get_ref_psi()
```

```
ket& qpp::QEngine::get_ref_psi ( ) [inline]
```

Reference to the underlying quantum state.

Returns

Reference to the underlying quantum state

7.56.3.13 get_relative_pos_()

```
\label{eq:condition} $$ std::vector < idx > qpp::QEngine::get_relative_pos_ ( \\ std::vector < idx > v ) [inline], [protected] $$
```

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

Parameters



Returns

Vector of qudit indexes

7.56.3.14 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

7.56.3.15 reset()

```
void qpp::QEngine::reset ( ) [inline]
```

Resets the engine.

Re-initializes everything to zero and sets the initial state to $|0\rangle^{\otimes n}$

7.56.3.16 set_dit()

Sets the classical dit at position i.

Parameters

i	Classical dit index
value	Classical dit value

Returns

Reference to the current instance

7.56.3.17 set_measured_()

Marks qudit *i* as measured then re-label accordingly the remaining non-measured qudits.

Parameters

```
i Qudit index
```

7.56.3.18 to_JSON()

qpp::IJOSN::to_JSON() override

Displays the state of the engine in JSON format

Parameters

```
enclosed_in_curly_brackets | If true, encloses the result in curly brackets
```

Returns

String containing the JSON representation of the state of the engine

Implements qpp::IJSON.

7.56.4 Member Data Documentation

```
7.56.4.1 dits_
std::vector<idx> qpp::QEngine::dits_ [protected]
classical dits

7.56.4.2 probs_
std::vector<double> qpp::QEngine::probs_ [protected]
measurement probabilities
```

```
7.56.4.3 psi_
ket qpp::QEngine::psi_ [protected]
state vector

7.56.4.4 qc_
const QCircuit* qpp::QEngine::qc_ [protected]
pointer to constant quantum circuit

7.56.4.5 subsys_
```

keeps track of the measured subsystems, relabel them after measurements

The documentation for this class was generated from the following file:

std::vector<idx> qpp::QEngine::subsys_ [protected]


classes/circuits.h

7.57 qpp::QubitAmplitudeDampingNoise Class Reference


Qubit amplitude damping noise, as described in Nielsen and Chuang.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitAmplitudeDampingNoise:



Collaboration diagram for qpp::QubitAmplitudeDampingNoise:



Public Member Functions

QubitAmplitudeDampingNoise (double gamma)
 Qubit amplitude damping noise constructor.

Additional Inherited Members

7.57.1 Detailed Description

Qubit amplitude damping noise, as described in Nielsen and Chuang.

7.57.2 Constructor & Destructor Documentation

7.57.2.1 QubitAmplitudeDampingNoise()

Qubit amplitude damping noise constructor.

Parameters

gamma	Amplitude damping probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.58 qpp::QubitBitFlipNoise Class Reference


Qubit bit flip noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitBitFlipNoise:



Collaboration diagram for qpp::QubitBitFlipNoise:



Public Member Functions

QubitBitFlipNoise (double p)
 Qubit bit flip noise constructor.

Additional Inherited Members

7.58.1 Detailed Description

Qubit bit flip noise.

7.58.2 Constructor & Destructor Documentation

7.58.2.1 QubitBitFlipNoise()

Qubit bit flip noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


classes/noise.h

7.59 qpp::QubitBitPhaseFlipNoise Class Reference


Qubit bit-phase flip (dephasing) noise.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitBitPhaseFlipNoise:



Collaboration diagram for qpp::QubitBitPhaseFlipNoise:



Public Member Functions

QubitBitPhaseFlipNoise (double p)
 Qubit bit-phase flip noise constructor.

Additional Inherited Members

7.59.1 Detailed Description

Qubit bit-phase flip (dephasing) noise.

7.59.2 Constructor & Destructor Documentation

7.59.2.1 QubitBitPhaseFlipNoise()

```
\label{eq:qpp::QubitBitPhaseFlipNoise::QubitBitPhaseFlipNoise (} \\ \mbox{double } p \mbox{ ) [inline], [explicit]}
```

Qubit bit-phase flip noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.60 qpp::QubitDepolarizingNoise Class Reference


Qubit depolarizing noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitDepolarizingNoise:



Collaboration diagram for qpp::QubitDepolarizingNoise:



Public Member Functions

QubitDepolarizingNoise (double p)
 Qubit depolarizing noise constructor.

Additional Inherited Members

7.60.1 Detailed Description

Qubit depolarizing noise.

7.60.2 Constructor & Destructor Documentation

7.60.2.1 QubitDepolarizingNoise()

```
\label{eq:qpp::QubitDepolarizingNoise::QubitDepolarizingNoise (} \\ \text{double } p \text{ ) } \quad \text{[inline], [explicit]}
```

Qubit depolarizing noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


classes/noise.h

7.61 qpp::QubitPhaseDampingNoise Class Reference


Qubit phase damping noise, as described in Nielsen and Chuang.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitPhaseDampingNoise:



Collaboration diagram for qpp::QubitPhaseDampingNoise:



Public Member Functions

QubitPhaseDampingNoise (double lambda)
 Qubit phase damping noise constructor.

Additional Inherited Members

7.61.1 Detailed Description

Qubit phase damping noise, as described in Nielsen and Chuang.

7.61.2 Constructor & Destructor Documentation

7.61.2.1 QubitPhaseDampingNoise()

Qubit phase damping noise constructor.

Parameters

gamma	Phase damping probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.62 qpp::QubitPhaseFlipNoise Class Reference


Qubit phase flip (dephasing) noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitPhaseFlipNoise:



Collaboration diagram for qpp::QubitPhaseFlipNoise:



Public Member Functions

QubitPhaseFlipNoise (double p)
 Qubit phase flip (dephasing) noise constructor.

Additional Inherited Members

7.62.1 Detailed Description

Qubit phase flip (dephasing) noise.

7.62.2 Constructor & Destructor Documentation

7.62.2.1 QubitPhaseFlipNoise()

Qubit phase flip (dephasing) noise constructor.

Parameters

```
p Noise probability
```

The documentation for this class was generated from the following file:


· classes/noise.h

7.63 qpp::exception::QuditAlreadyMeasured Class Reference


Qudit was already measured exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::QuditAlreadyMeasured:



Collaboration diagram for qpp::exception::QuditAlreadyMeasured:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.63.1 Detailed Description

Qudit was already measured exception.

The qudit was already measured and cannot be measured again

7.63.2 Member Function Documentation

7.63.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.63.2.2 type_description()

std::string qpp::exception::QuditAlreadyMeasured::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.64 qpp::QuditDepolarizingNoise Class Reference


Qudit depolarizing noise.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QuditDepolarizingNoise:



Collaboration diagram for qpp::QuditDepolarizingNoise:



Public Member Functions

QuditDepolarizingNoise (double p, idx d)
 Qudit depolarizing noise constructor.

Private Member Functions

• std::vector< cmat > fill_Ks_ (idx d) const

Fills the Kraus operator vector.

std::vector< double > fill_probs_ (double p, idx d) const
 Fills the probability vector.

Additional Inherited Members

7.64.1 Detailed Description

Qudit depolarizing noise.

7.64.2 Constructor & Destructor Documentation

7.64.2.1 QuditDepolarizingNoise()

Qudit depolarizing noise constructor.

Parameters

р	Noise probability
d	Subsystem dimension

7.64.3 Member Function Documentation

Fills the Kraus operator vector.

Parameters

d Qudit dimension

Returns

Vector of Kraus operators representing the depolarizing noise

7.64.3.2 fill_probs_()

Fills the probability vector.

Parameters

р	Probability
d	Qudit dimension

Returns

Probability vector

The documentation for this class was generated from the following file:


• classes/noise.h

7.65 qpp::RandomDevices Class Reference


Singleton class that manages the source of randomness in the library.

#include <classes/random_devices.h>

Inheritance diagram for qpp::RandomDevices:



Collaboration diagram for qpp::RandomDevices:



Public Member Functions

• std::mt19937 & get_prng ()

Returns a reference to the internal PRNG object.

std::istream & load (std::istream &is)

Loads the state of the PRNG from an input stream.

• std::ostream & save (std::ostream &os) const

Saves the state of the PRNG to an output stream.

Private Member Functions

• RandomDevices ()

Initializes and seeds the random number generators.

∼RandomDevices ()=default

Default destructor.

Private Attributes

 std::random_device rd_ used to seed std::mt19937 prng_

std::mt19937 prng_

Mersenne twister random number generator.

Friends

class internal::Singleton < RandomDevices >

Additional Inherited Members

7.65.1 Detailed Description

Singleton class that manages the source of randomness in the library.

Warning

This class DOES NOT seed the standard C number generator used by Eigen::Matrix::Random(), since it is not thread safe. Do not use Eigen::Matrix::Random() or functions that depend on the C style random number engine, but use qpp::rand() instead!

7.65.2 Constructor & Destructor Documentation

7.65.2.1 RandomDevices()

```
qpp::RandomDevices::RandomDevices ( ) [inline], [private]
```

Initializes and seeds the random number generators.

```
7.65.2.2 ∼RandomDevices()
```

```
\verb"qpp::RandomDevices::$\sim$RandomDevices ( ) [private], [default]
```

Default destructor.

7.65.3 Member Function Documentation

```
7.65.3.1 get_prng()
```

```
std::mt19937& qpp::RandomDevices::get_prng ( ) [inline]
```

Returns a reference to the internal PRNG object.

Returns

Reference to the internal PRNG object

7.65.3.2 load()

Loads the state of the PRNG from an input stream.

Parameters

```
is Input stream
```

Returns

The input stream

7.65.3.3 save()

Saves the state of the PRNG to an output stream.

Parameters

os Output stream

Returns

The output stream

7.65.4 Friends And Related Function Documentation

```
7.65.4.1 internal::Singleton < Random Devices >
```

```
friend class internal::Singleton< RandomDevices > [friend]
```

7.65.5 Member Data Documentation

```
7.65.5.1 prng_
```

```
std::mt19937 qpp::RandomDevices::prng_ [private]
```

Mersenne twister random number generator.

```
7.65.5.2 rd_
```

```
std::random_device qpp::RandomDevices::rd_ [private]
```

used to seed std::mt19937 prng_

The documentation for this class was generated from the following file:

• classes/random_devices.h

7.66 qpp::internal::Singleton < T > Class Template Reference

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

```
#include <internal/classes/singleton.h>
```

Static Public Member Functions

- static T & get_instance () noexcept(std::is_nothrow_constructible < T >::value)
- static T & get_thread_local_instance () noexcept(std::is_nothrow_constructible < T >::value)

Protected Member Functions

- Singleton () noexcept=default
- Singleton (const Singleton &)=delete
- Singleton & operator= (const Singleton &)=delete
- virtual ∼Singleton ()=default

7.66.1 Detailed Description

```
\label{template} \begin{tabular}{ll} template < typename T > \\ class & qpp::internal::Singleton < T > \\ \end{tabular}
```

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

To implement a singleton, derive your class from qpp::internal::Singleton, make qpp::internal::Singleton a friend of your class, then declare the constructor and destructor of your class as private. To get an instance, use the static member function qpp::internal::Singleton::get_instance() (qpp::internal::Singleton::get_thread_local_instance()), which returns a reference (thread_local_reference) to your newly created singleton (thread-safe in C++11).

Example:

See also

Code of qpp::Codes, qpp::Gates, qpp::Init, qpp::RandomDevices, qpp::States or qpp.h for real world examples of usage.

7.66.2 Constructor & Destructor Documentation

```
7.66.2.1 Singleton() [1/2]
template<typename T>
qpp::internal::Singleton < T >::Singleton ( ) [protected], [default], [noexcept]
7.66.2.2 Singleton() [2/2]
template<typename T>
qpp::internal::Singleton < T >::Singleton (
             const Singleton< T > \& ) [protected], [delete]
7.66.2.3 ∼Singleton()
template<typename T>
virtual qpp::internal::Singleton < T >::~Singleton ( ) [protected], [virtual], [default]
7.66.3 Member Function Documentation
7.66.3.1 get_instance()
template<typename T>
\texttt{static} \ \texttt{T\& qpp::internal::Singleton} < \ \texttt{T} \ > :: \texttt{get\_instance} \ ( \ ) \quad \texttt{[inline], [static], [noexcept]}
7.66.3.2 get_thread_local_instance()
template<typename T>
static T& qpp::internal::Singleton< T >::get_thread_local_instance ( ) [inline], [static],
[noexcept]
7.66.3.3 operator=()
template<typename T>
Singleton& qpp::internal::Singleton< T >::operator= (
              const Singleton< T > \& ) [protected], [delete]
```

The documentation for this class was generated from the following file:


• internal/classes/singleton.h

7.67 qpp::exception::SizeMismatch Class Reference

Size mismatch exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SizeMismatch:



Collaboration diagram for qpp::exception::SizeMismatch:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.67.1 Detailed Description

Size mismatch exception.

Sizes do not match

7.67.2 Member Function Documentation

7.67.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.67.2.2 type_description()

std::string qpp::exception::SizeMismatch::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

7.68 qpp::NoiseType::StateDependent Class Reference

Template tag, used whenever the noise is state-dependent.

#include <classes/noise.h>

7.68.1 Detailed Description

Template tag, used whenever the noise is state-dependent.

The documentation for this class was generated from the following file:

· classes/noise.h

7.69 qpp::NoiseType::StateIndependent Class Reference

Template tag, used whenever the noise is state-independent.

#include <classes/noise.h>

7.69.1 Detailed Description

Template tag, used whenever the noise is state-independent.

The documentation for this class was generated from the following file:


classes/noise.h

7.70 qpp::States Class Reference


const Singleton class that implements most commonly used states

#include <classes/states.h>

Inheritance diagram for qpp::States:



Collaboration diagram for qpp::States:



Public Member Functions

• ket mes (idx d=2) const

Maximally entangled state of 2 qudits.

• ket zero (idx n, idx d=2) const

Zero state of n qudits.

• ket one (idx n, idx d=2) const

One state of n qudits.

• ket jn (idx j, idx n, idx d=2) const

 $|j\rangle^{\otimes n}$ state of n qudits

• ket plus (idx n) const

Plus state of n qubits.

• ket minus (idx n) const

Minus state of n qubits.

Public Attributes

```
    ket x0 {ket::Zero(2)}
```

Pauli Sigma-X 0-eigenstate |+>

ket x1 {ket::Zero(2)}

Pauli Sigma-X 1-eigenstate |->

ket y0 {ket::Zero(2)}

Pauli Sigma-Y 0-eigenstate |y+>

ket y1 {ket::Zero(2)}

Pauli Sigma-Y 1-eigenstate | y->

ket z0 {ket::Zero(2)}

Pauli Sigma-Z 0-eigenstate | 0>

ket z1 {ket::Zero(2)}

Pauli Sigma-Z 1-eigenstate | 1>

• cmat px0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

• cmat px1 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.

```
    cmat py0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 0-eigenstate |y+\rangle < y+|.

    cmat py1 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.

    cmat pz0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
• cmat pz1 {cmat::Zero(2, 2)}
      Projector onto the Pauli Sigma-Z 1-eigenstate |1><1|.

    ket b00 {ket::Zero(4)}

      Bell-00 state, as described in Nielsen and Chuang.

    ket b01 {ket::Zero(4)}

      Bell-01 state, as described in Nielsen and Chuang.

    ket b10 {ket::Zero(4)}

      Bell-10 state, as described in Nielsen and Chuang.
ket b11 {ket::Zero(4)}
      Bell-11 state, as described in Nielsen and Chuang.

    cmat pb00 {cmat::Zero(4, 4)}

      Projector onto the Bell-00 state.

    cmat pb01 {cmat::Zero(4, 4)}

      Projector onto the Bell-01 state.

    cmat pb10 {cmat::Zero(4, 4)}

      Projector onto the Bell-10 state.

    cmat pb11 {cmat::Zero(4, 4)}

      Projector onto the Bell-11 state.
ket GHZ {ket::Zero(8)}
      GHZ state.

    ket W {ket::Zero(8)}

      W state.
cmat pGHZ {cmat::Zero(8, 8)}
      Projector onto the GHZ state.
cmat pW {cmat::Zero(8, 8)}
      Projector onto the W state.
```

Private Member Functions

- States ()
- ∼States ()=default

Default destructor.

Friends

class internal::Singleton < const States >

Additional Inherited Members

7.70.1 Detailed Description

const Singleton class that implements most commonly used states

7.70.2 Constructor & Destructor Documentation

```
7.70.2.1 States()

qpp::States::States ( ) [inline], [private]

Initialize the states

7.70.2.2 ~States()

qpp::States::~States ( ) [private], [default]
```

7.70.3 Member Function Documentation

```
7.70.3.1 jn()
```

Default destructor.

 $|j\rangle^{\otimes n}$ state of *n* qudits

Parameters

j	Non-negative integer
n	Non-negative integer
d	Subsystem dimensions

Returns

 $|j\rangle^{\otimes n}$ state of *n* qudits

7.70.3.2 mes()

```
ket qpp::States::mes (
idx d = 2 ) const [inline]
```

Maximally entangled state of 2 qudits.

Parameters

d Subsystem dimensions

Returns

Maximally entangled state $\frac{1}{\sqrt{d}} \sum_{j=0}^{d-1} |jj\rangle$ of 2 qudits

7.70.3.3 minus()

```
ket qpp::States::minus (
          idx n ) const [inline]
```

Minus state of *n* qubits.

Parameters

n Non-negative integer

Returns

Minus state $|-\rangle^{\otimes n}$ of n qubits

7.70.3.4 one()

```
ket qpp::States::one (
          idx n,
          idx d = 2) const [inline]
```

One state of *n* qudits.

Parameters

n	Non-negative integer
d	Subsystem dimensions

Returns

One state $|1\rangle^{\otimes n}$ of n qudits

7.70.3.5 plus()

```
ket qpp::States::plus (
         idx n ) const [inline]
```

Plus state of *n* qubits.

Parameters

```
n Non-negative integer
```

Returns

Plus state $|+\rangle^{\otimes n}$ of n qubits

7.70.3.6 zero()

```
ket qpp::States::zero (
         idx n,
         idx d = 2 ) const [inline]
```

Zero state of *n* qudits.

Parameters

n	Non-negative integer
d	Subsystem dimensions

Returns

Zero state $|0\rangle^{\otimes n}$ of n qudits

7.70.4 Friends And Related Function Documentation

```
7.70.4.1 internal::Singleton < const States >
```

friend class internal::Singleton< const States > [friend]

7.70.5 Member Data Documentation

```
7.70.5.1 b00
```

```
ket qpp::States::b00 {ket::Zero(4)}
```

Bell-00 state, as described in Nielsen and Chuang.

7.70.5.2 b01

```
ket qpp::States::b01 {ket::Zero(4)}
```

Bell-01 state, as described in Nielsen and Chuang.

7.70.5.3 b10

```
ket qpp::States::b10 {ket::Zero(4)}
```

Bell-10 state, as described in Nielsen and Chuang.

7.70.5.4 b11

```
ket qpp::States::b11 {ket::Zero(4)}
```

Bell-11 state, as described in Nielsen and Chuang.

7.70.5.5 GHZ

```
ket qpp::States::GHZ {ket::Zero(8)}
```

GHZ state.

7.70.5.6 pb00

```
cmat qpp::States::pb00 {cmat::Zero(4, 4)}
```

Projector onto the Bell-00 state.

```
7.70.5.7 pb01
cmat qpp::States::pb01 {cmat::Zero(4, 4)}
Projector onto the Bell-01 state.
7.70.5.8 pb10
cmat qpp::States::pb10 {cmat::Zero(4, 4)}
Projector onto the Bell-10 state.
7.70.5.9 pb11
cmat qpp::States::pb11 {cmat::Zero(4, 4)}
Projector onto the Bell-11 state.
7.70.5.10 pGHZ
cmat qpp::States::pGHZ {cmat::Zero(8, 8)}
Projector onto the GHZ state.
7.70.5.11 pW
cmat qpp::States::pW {cmat::Zero(8, 8)}
Projector onto the W state.
7.70.5.12 px0
cmat qpp::States::px0 {cmat::Zero(2, 2)}
```

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

```
7.70.5.13 px1
cmat qpp::States::px1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.
7.70.5.14 py0
cmat qpp::States::py0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 0-eigenstate |y+>< y+|.
7.70.5.15 py1
cmat qpp::States::py1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.
7.70.5.16 pz0
cmat qpp::States::pz0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
7.70.5.17 pz1
cmat qpp::States::pz1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 1-eigenstate |1><1|.
7.70.5.18 W
ket qpp::States::W {ket::Zero(8)}
W state.
```

```
7.70.5.19 x0
ket qpp::States::x0 {ket::Zero(2)}
Pauli Sigma-X 0-eigenstate |+>
7.70.5.20 x1
ket qpp::States::x1 {ket::Zero(2)}
Pauli Sigma-X 1-eigenstate |->
7.70.5.21 y0
ket qpp::States::y0 {ket::Zero(2)}
Pauli Sigma-Y 0-eigenstate |y+>
7.70.5.22 y1
ket qpp::States::y1 {ket::Zero(2)}
Pauli Sigma-Y 1-eigenstate |y->
7.70.5.23 z0
ket qpp::States::z0 {ket::Zero(2)}
Pauli Sigma-Z 0-eigenstate |0>
7.70.5.24 z1
ket qpp::States::z1 {ket::Zero(2)}
Pauli Sigma-Z 1-eigenstate |1>
The documentation for this class was generated from the following file:
```


classes/states.h

7.71 qpp::exception::SubsysMismatchDims Class Reference


Subsystems mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SubsysMismatchDims:



Collaboration diagram for qpp::exception::SubsysMismatchDims:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.71.1 Detailed Description

Subsystems mismatch dimensions exception.

std::vector<idx> of subsystem labels has duplicates, or has entries that are larger than the size of the std← ::vector<idx> of dimensions

7.71.2 Member Function Documentation

7.71.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

Text representing where the exception of	П
--	---

7.71.2.2 type_description()

```
std::string qpp::exception::SubsysMismatchDims::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.72 qpp::Timer < T, CLOCK_T > Class Template Reference


Chronometer.

#include <classes/timer.h>

Inheritance diagram for qpp::Timer< T, CLOCK_T >:



Collaboration diagram for qpp::Timer < T, CLOCK_T >:



Public Member Functions

· Timer () noexcept

Constructs an instance with the current time as the starting point.

• void tic () noexcept

Resets the chronometer.

• const Timer & toc () noexcept

Stops the chronometer.

· double tics () const noexcept

Time passed in the duration specified by T.

• template<typename U = T>

U get_duration () const noexcept

Duration specified by U.

Timer (const Timer &)=default

Default copy constructor.

• Timer (Timer &&)=default

Default move constructor.

• Timer & operator= (const Timer &)=default

Default copy assignment operator.

• Timer & operator= (Timer &&)=default

Default move assignment operator.

virtual ∼Timer ()=default

Default virtual destructor.

Protected Attributes

- CLOCK_T::time_point start_
- CLOCK_T::time_point end

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display() override*

7.72.1 Detailed Description

```
template < typename\ T = std::chrono::duration < double >, typename\ CLOCK\_T = std::chrono::steady\_clock > class\ qpp::Timer < T,\ CLOCK\_T >
```

Chronometer.

Template Parameters

T	Tics duration, default is std::chrono::duration <double, 1="">, i.e. seconds in double precision</double,>
CLOCK← T	Clock's type, default is std::chrono::steady_clock, not affected by wall clock changes during runtime

7.72.2 Constructor & Destructor Documentation

```
7.72.2.1 Timer() [1/3]
```

```
\label{lock-type-ame} $$ $$ template<type-name T = std::chrono::steady \leftarrow \_clock> $$ $$ qpp::Timer< T, CLOCK_T >::Timer ( ) [inline], [noexcept] $$
```

Constructs an instance with the current time as the starting point.

7.72.2.2 Timer() [2/3]

Default copy constructor.

7.72.2.3 Timer() [3/3]

Default move constructor.

7.72.2.4 \sim Timer()

```
\label{template} $$ \ensuremath{\sf template}$ $$ \ensurem
```

Default virtual destructor.

7.72.3 Member Function Documentation

7.72.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream the number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc().

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.72.3.2 get_duration()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
template<typename U = T>
U qpp::Timer< T, CLOCK_T >::get_duration ( ) const [inline], [noexcept]
```

Duration specified by U.

Template Parameters

U Duration, default is T, which defaults to std::chrono::duration<double, 1>, i.e. seconds in double precision

Returns

Duration that passed between the instantiation/reset and invocation of qpp::Timer::toc()

```
7.72.3.3 operator=() [1/2]
```

Default copy assignment operator.

```
7.72.3.4 operator=() [2/2]
```

Default move assignment operator.

7.72.3.5 tic()

Resets the chronometer.

Resets the starting/ending point to the current time

7.72.3.6 tics()

```
\label{lock_typename} $$ $$ template< typename T = std::chrono::steady \leftarrow \_clock> $$ double $$ qpp::Timer< T, CLOCK_T >::tics ( ) const [inline], [noexcept] $$
```

Time passed in the duration specified by T.

Returns

Number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc()

7.72.3.7 toc()

```
\label{lock-type-ame} $$ $$ template<typename T = std::chrono::steady \leftarrow \_clock> $$ const Timer& qpp::Timer< T, CLOCK_T >::toc ( ) [inline], [noexcept] $$
```

Stops the chronometer.

Set the current time as the ending point

Returns

Reference to the current instance

7.72.4 Member Data Documentation

7.72.4.1 end

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::end_ [protected]
```

7.72.4.2 start_

```
\label{lock_typename} $$ $$ template < typename $$ CLOCK_T = std::chrono::steady \hookrightarrow \_clock > $$ CLOCK_T::time\_point $$ qpp::Timer < T, CLOCK_T >::start_ [protected] $$
```

The documentation for this class was generated from the following file:


· classes/timer.h

7.73 qpp::exception::TypeMismatch Class Reference


Type mismatch exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::TypeMismatch:



Collaboration diagram for qpp::exception::TypeMismatch:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.73.1 Detailed Description

Type mismatch exception.

Scalar types do not match

7.73.2 Member Function Documentation

7.73.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.73.2.2 type_description()

std::string qpp::exception::TypeMismatch::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.74 qpp::exception::UndefinedType Class Reference


Not defined for this type exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::UndefinedType:



Collaboration diagram for qpp::exception::UndefinedType:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.74.1 Detailed Description

Not defined for this type exception.

Templated specialization is not defined for this type

7.74.2 Member Function Documentation

7.74.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.74.2.2 type_description()

std::string qpp::exception::UndefinedType::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


• classes/exception.h

7.75 qpp::exception::Unknown Class Reference


Unknown exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Unknown:



Collaboration diagram for qpp::exception::Unknown:



Public Member Functions

- std::string type_description () const override
 Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.75.1 Detailed Description

Unknown exception.

Thrown when no other exception is suitable (not recommended, it is better to define another suitable exception type)

7.75.2 Member Function Documentation

7.75.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.75.2.2 type_description()

std::string qpp::exception::Unknown::type_description () const [inline], [override], [virtual]
Exception type description.

Returns

Exception type description


Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.76 qpp::QCircuit::iterator::value_type_ Class Reference

Inheritance diagram for qpp::QCircuit::iterator::value_type_:



Collaboration diagram for qpp::QCircuit::iterator::value_type_:



Public Member Functions

```
    value_type_ (const QCircuit *value_type_qc)
        Default value_type_ constructor.
    value_type_ (const value_type_ &)=default
        Default copy constructor.
    value_type_ & operator= (const value_type_ &)=default
        Default copy assignment operator.
```

Public Attributes

```
    const QCircuit * value_type_qc_
        < non-owning pointer to the parent iterator</li>
    StepType type_{StepType::NONE}
        step type
    idx ip_{static_cast<idx>(-1)}
        instruction pointer
    std::vector< GateStep >::const_iterator gates_ip_{gates instruction pointer}
    std::vector< MeasureStep >::const_iterator measurements_ip_{measurements instruction pointer}
```

Private Member Functions

7.76.1 Constructor & Destructor Documentation

```
7.76.1.2 value_type_() [2/2]
qpp::QCircuit::iterator::value_type_::value_type_ (
```

```
const value_type_ & ) [default]
```

Default copy constructor.

7.76.2 Member Function Documentation

```
7.76.2.1 display()
```

qpp::IDisplay::display() override

Writes to the output stream the textual representation of the iterator de-referenced element

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.76.2.2 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

7.76.3 Member Data Documentation

```
7.76.3.1 gates_ip_
std::vector<GateStep>::const_iterator qpp::QCircuit::iterator::value_type_::gates_ip_ {}
gates instruction pointer
```

```
7.76.3.2 ip_
idx qpp::QCircuit::iterator::value_type_::ip_ {static_cast<idx>(-1)}
instruction pointer
7.76.3.3 measurements_ip_
\verb|std::vector<| MeasureStep| > ::const_iterator | qpp::QCircuit::iterator::value_type_::measurements\_{\leftarrow}| | qpp::QCircuit::qt_iterator::value_type_::qt_iterator::value_type_::qt_iterator::value_type_::qt_iterator::value_type_::qt_iterator::value_type_::qt_iterator::value_type_::qt_iterator::value_type_:
ip_ {}
measurements instruction pointer
7.76.3.4 type_
StepType qpp::QCircuit::iterator::value_type_::type_ {StepType::NONE}
step type
7.76.3.5 value_type_qc_
const QCircuit* qpp::QCircuit::iterator::value_type_::value_type_qc_
 < non-owning pointer to the parent iterator
The documentation for this class was generated from the following file:
```

Generated by Doxygen


· classes/circuits.h

7.77 qpp::exception::ZeroSize Class Reference


Object has zero size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::ZeroSize:



Collaboration diagram for qpp::exception::ZeroSize:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.77.1 Detailed Description

Object has zero size exception.

Zero sized object, e.g. empty Eigen::Matrix or std::vector with no elements

7.77.2 Member Function Documentation

7.77.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.77.2.2 type_description()

std::string qpp::exception::ZeroSize::type_description () const [inline], [override], [virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h


Chapter 8

File Documentation

8.1 classes/circuits.h File Reference

Support for qudit quantum circuits.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::QCircuit

Quantum circuit class.

• struct qpp::QCircuit::GateStep

One step consisting only of gates/operators in the circuit.

struct qpp::QCircuit::MeasureStep

One step consisting only of measurements in the circuit.

· class qpp::QCircuit::iterator

Quantum circuit bound-checking (safe) iterator.

- class qpp::QCircuit::iterator::value_type_
- class qpp::QEngine

Quantum circuit engine, executes qpp::QCircuit.

356 File Documentation

Namespaces

• qpp

Quantum++ main namespace.


8.1.1 Detailed Description

Support for qudit quantum circuits.

8.2 classes/codes.h File Reference

Quantum error correcting codes.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::Codes

const Singleton class that defines quantum error correcting codes

Namespaces

• qpp

Quantum++ main namespace.


8.2.1 Detailed Description

Quantum error correcting codes.

8.3 classes/exception.h File Reference

Exceptions.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::exception::Exception

Base class for generating Quantum++ custom exceptions.

· class qpp::exception::Unknown

Unknown exception.

class qpp::exception::ZeroSize

Object has zero size exception.

• class qpp::exception::MatrixNotSquare

Matrix is not square exception.

class qpp::exception::MatrixNotCvector

Matrix is not a column vector exception.

· class qpp::exception::MatrixNotRvector

Matrix is not a row vector exception.

class qpp::exception::MatrixNotVector

Matrix is not a vector exception.

class qpp::exception::MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

• class qpp::exception::MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

· class qpp::exception::MatrixNotSquareNorVector

Matrix is not square nor vector exception.

class qpp::exception::MatrixMismatchSubsys

Matrix mismatch subsystems exception.

· class qpp::exception::DimsInvalid

Invalid dimension(s) exception.

class qpp::exception::DimsNotEqual

Dimensions not equal exception.

class qpp::exception::DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

class qpp::exception::DimsMismatchCvector

358 File Documentation

Dimension(s) mismatch column vector size exception.

· class qpp::exception::DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

class qpp::exception::DimsMismatchVector

Dimension(s) mismatch vector size exception.

class qpp::exception::SubsysMismatchDims

Subsystems mismatch dimensions exception.

· class qpp::exception::PermInvalid

Invalid permutation exception.

class qpp::exception::PermMismatchDims

Permutation mismatch dimensions exception.

· class qpp::exception::NotQubitMatrix

Matrix is not 2 x 2 exception.

class qpp::exception::NotQubitCvector

Column vector is not 2 x 1 exception.

class qpp::exception::NotQubitRvector

Row vector is not 1 x 2 exception.

class qpp::exception::NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

• class qpp::exception::NotQubitSubsys

Subsystems are not qubits exception.

· class qpp::exception::NotBipartite

Not bi-partite exception.

· class qpp::exception::NoCodeword

Codeword does not exist exception.

· class qpp::exception::OutOfRange

Argument out of range exception.

· class qpp::exception::TypeMismatch

Type mismatch exception.

• class qpp::exception::SizeMismatch

Size mismatch exception.

class qpp::exception::UndefinedType

Not defined for this type exception.

· class qpp::exception::QuditAlreadyMeasured

Qudit was already measured exception.

· class qpp::exception::Duplicates

System (e.g. std::vector) has duplicates exception.

· class qpp::exception::CustomException

Custom exception.

· class qpp::exception::NotImplemented

Code not yet implemented.

· class qpp::exception::InvalidIterator

Invalid iterator.

Namespaces

qpp

Quantum++ main namespace.

• qpp::exception

Quantum++ exception hierarchy namespace.


8.3.1 Detailed Description

Exceptions.

8.4 classes/gates.h File Reference

Quantum gates.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::Gates

const Singleton class that implements most commonly used gates

Namespaces

• qpp

Quantum++ main namespace.

8.4.1 Detailed Description


Quantum gates.

360 File Documentation

8.5 classes/idisplay.h File Reference

Display interface via the non-virtual interface (NVI) and very basic JSON serialization support interface.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

class qpp::IJSON

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

Namespaces

• qpp

Quantum++ main namespace.


8.5.1 Detailed Description

Display interface via the non-virtual interface (NVI) and very basic JSON serialization support interface.

8.6 classes/init.h File Reference

Initialization.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::Init

const Singleton class that performs additional initializations/cleanups

Namespaces

• qpp

Quantum++ main namespace.


8.6.1 Detailed Description

Initialization.

8.7 classes/noise.h File Reference

Noise models.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::NoiseType

Contains template tags used to specify the noise type.

class qpp::NoiseBase< T >

Base class for all noise models, derive your particular noise model.

class qpp::QubitDepolarizingNoise

Qubit depolarizing noise.

· class qpp::QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

· class qpp::QubitBitFlipNoise

Qubit bit flip noise.

· class qpp::QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

· class qpp::QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

· class qpp::QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

· class qpp::QuditDepolarizingNoise

Qudit depolarizing noise.

Namespaces

• qpp

Quantum++ main namespace.


8.7.1 Detailed Description

Noise models.

8.8 classes/random_devices.h File Reference

Random devices.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::RandomDevices

Singleton class that manages the source of randomness in the library.

Namespaces

• qpp

Quantum++ main namespace.


8.8.1 Detailed Description

Random devices.

8.9 classes/reversible.h File Reference

Support for classical reversible circuits.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::Dynamic_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

class qpp::Bit_circuit

Classical reversible circuit simulator.

• struct qpp::Bit_circuit::Gate_count

Namespaces

qpp

Quantum++ main namespace.


8.9.1 Detailed Description

Support for classical reversible circuits.

8.10 classes/states.h File Reference

Quantum states.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::States

const Singleton class that implements most commonly used states

Namespaces

• qpp

Quantum++ main namespace.


8.10.1 Detailed Description

Quantum states.

8.11 classes/timer.h File Reference

Timing.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::Timer < T, CLOCK_T >
 Chronometer.

Namespaces

• qpp

Quantum++ main namespace.


8.11.1 Detailed Description

Timing.

8.12 constants.h File Reference

Constants.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

• qpp::literals

Functions

- constexpr cplx qpp::literals::operator"" _i (unsigned long long int x) noexcept User-defined literal for complex $i=\sqrt{-1}$ (integer overload)
- constexpr cplx qpp::operator"" _i (long double x) noexcept

User-defined literal for complex $i = \sqrt{-1}$ (real overload)

• cplx qpp::omega (idx D)

D-th root of unity.

Variables

• constexpr double qpp::chop = 1e-10

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

• constexpr idx qpp::maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

• constexpr double qpp::pi = 3.141592653589793238462643383279502884

 π

• constexpr double qpp::ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

• constexpr double qpp::infty = std::numeric_limits<double>::max()

Used to denote infinity in double precision.


8.12.1 Detailed Description

Constants.

8.13 entanglement.h File Reference

Entanglement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

```
    template<typename Derived >

  dyn col vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector<
  idx > &dims)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  dyn_col_vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  cmat qpp::schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat qpp::schmidtA (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Bob side.

    template<typename Derived >

  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Bob side.
• template<typename Derived >
  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx
  > &dims)
      Schmidt probabilities of the bi-partite pure state A.

    template<typename Derived >

  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt probabilities of the bi-partite pure state A.
• template<typename Derived >
  double qpp::entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Entanglement of the bi-partite pure state A.
• template<typename Derived >
  double <a href="mailto:qpp::entanglement">qpp::entanglement</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Entanglement of the bi-partite pure state A.

    template<typename Derived >

  double <a href="mailto:qpp::gconcurrence">qpp::gconcurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      G-concurrence of the bi-partite pure state A.

    template<typename Derived >

  double qpp::negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double <a href="mailto:qpp::negativity">qpp::negativity</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double <a href="mailto:qpp::concurrence">qpp::concurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.
```


8.13.1 Detailed Description

Entanglement functions.

8.14 entropies.h File Reference

Entropy functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

```
    template < typename Derived >
        double qpp::entropy (const Eigen::MatrixBase < Derived > &A)
```

von-Neumann entropy of the density matrix A

double qpp::entropy (const std::vector< double > &prob)

Shannon entropy of the probability distribution prob.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

```
double <a href="mailto:qpp::renyi">qpp::renyi</a> (const Eigen::MatrixBase< Derived > &A, double alpha)
```

Renyi- α entropy of the density matrix A, for $\alpha \geq 0$.

double qpp::renyi (const std::vector< double > &prob, double alpha)

Renyi- α entropy of the probability distribution prob, for $\alpha \geq 0$.

template<typename Derived >

```
double <a href="mailto:qpp::tsallis">qpp::tsallis</a> (const Eigen::MatrixBase< Derived > &A, double q)
```

Tsallis- q entropy of the density matrix A, for $q \geq 0$.

double qpp::tsallis (const std::vector< double > &prob, double q)

Tsallis- q entropy of the probability distribution prob, for $q \geq 0$.

• template<typename Derived >

double qpp::qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const std::vector< idx > &subsysB, const std::vector< idx > &dims)

Quantum mutual information between 2 subsystems of a composite system.

• template<typename Derived >

 $\label{lem:double qpp::qmutualinfo} $$ double qpp::qmutualinfo (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &subsysA, const std::vector < idx > &subsysB, idx d=2) $$$

Quantum mutual information between 2 subsystems of a composite system.

8.14.1 Detailed Description

Entropy functions.

8.15 experimental/experimental.h File Reference

Experimental/test functions/classes.

Namespaces

• qpp

Quantum++ main namespace.

qpp::experimental

Experimental/test functions/classes, do not use or modify.


8.15.1 Detailed Description

Experimental/test functions/classes.

8.16 functions.h File Reference

Generic quantum computing functions.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::internal::HashEigen

Functor for hashing Eigen expressions.

• class qpp::internal::KeyEqualEigen

Functor for comparing Eigen expressions.

Namespaces

qpp

Quantum++ main namespace.

- · qpp::literals
- qpp::internal

Eigenvectors.

Internal utility functions, do not use them directly or modify them.

Functions

```
    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::transpose (const Eigen::MatrixBase< Derived > &A)
      Transpose.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::adjoint (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::inverse (const Eigen::MatrixBase< Derived > &A)
      Inverse.

    template < typename Derived >

  Derived::Scalar qpp::trace (const Eigen::MatrixBase< Derived > &A)
      Trace.
• template<typename Derived >
  Derived::Scalar qpp::det (const Eigen::MatrixBase< Derived > &A)
      Determinant.

    template<typename Derived >

  Derived::Scalar <a href="mailto:qpp::logdet">qpp::logdet</a> (const Eigen::MatrixBase</a> Derived > &A)
      Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar <a href="mailto:qpp::sum">qpp::sum</a> (const Eigen::MatrixBase< Derived > &A)
      Element-wise sum of A.
• template<typename Derived >
  Derived::Scalar <a href="mailto:open:prod">open:prod</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise product of A.

    template<typename Derived >

  double <a href="mailto:qpp::norm">qpp::norm</a> (const Eigen::MatrixBase< Derived > &A)
     Frobenius norm.

    template < typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::normalize (const Eigen::MatrixBase< Derived > &A)
      Normalizes state vector (column or row vector) or density matrix.

    template<typename Derived >

  std::pair< dyn_col_vect< cplx >, cmat > qpp::eig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition.
• template<typename Derived >
  dyn_col_vect< cplx > qpp::evals (const Eigen::MatrixBase< Derived > &A)
      Eigenvalues.

    template<typename Derived >

  cmat qpp::evects (const Eigen::MatrixBase< Derived > &A)
```

```
• template<typename Derived >
  std::pair< dyn_col_vect< double >, cmat > qpp::heig (const Eigen::MatrixBase< Derived > &A)
     Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > qpp::hevals (const Eigen::MatrixBase< Derived > &A)
     Hermitian eigenvalues.
• template<typename Derived >
  cmat qpp::hevects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors of Hermitian matrix.
• template<typename Derived >
  std::tuple< cmat, dyn col vect< double >, cmat > qpp::svd (const Eigen::MatrixBase< Derived > &A)
     Full singular value decomposition.
• template<typename Derived >
  dyn_col_vect< double > qpp::svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.

    template<typename Derived >

  cmat qpp::svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.

    template<typename Derived >

  cmat qpp::svdV (const Eigen::MatrixBase< Derived > &A)
     Right singular vectors.

    template<typename Derived >

  cmat qpp::funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)
• template<typename Derived >
  cmat qpp::sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.
• template<typename Derived >
  cmat qpp::absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.

    template<typename Derived >

  cmat qpp::expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.
• template<typename Derived >
  cmat qpp::logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.
• template<typename Derived >
  cmat qpp::sinm (const Eigen::MatrixBase< Derived > &A)
     Matrix sin.

    template<typename Derived >

  cmat qpp::cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.

    template<typename Derived >

  cmat qpp::spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::powm (const Eigen::MatrixBase< Derived > &A, idx n)
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

    template<typename Derived >

  double qpp::schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > qpp::cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const
  typename Derived::Scalar &))
```

```
Functor.
• template<typename T >
  dyn_mat< typename T::Scalar > qpp::kron (const T &head)
     Kronecker product.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > qpp::kron (const T &head, const Args &... tail)
     Kronecker product.
• template<typename Derived >
  dyn mat< typename Derived::Scalar > qpp::kron (const std::vector< Derived > &As)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::kron (const std::initializer_list< Derived > &As)
     Kronecker product.

    template < typename Derived >

  dyn mat< typename Derived::Scalar > qpp::kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Kronecker power.
template<typename T >
  dyn_mat< typename T::Scalar > qpp::dirsum (const T &head)
     Direct sum.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > qpp::dirsum (const T &head, const Args &... tail)
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::vector< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::initializer_list< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::reshape (const Eigen::MatrixBase< Derived > &A, idx rows,
  idx cols)
     Reshape.

    template<typename Derived1 , typename Derived2 >

  dyn mat< typename Derived1::Scalar > qpp::comm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Commutator.

    template<typename Derived1 , typename Derived2 >

  dyn mat< typename Derived1::Scalar > qpp::anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.
ullet template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::prj (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::grams (const std::vector< Derived > &As)
     Gram-Schmidt orthogonalization.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::grams (const std::initializer_list< Derived > &As)
     Gram-Schmidt orthogonalization.
```

dyn_mat< typename Derived::Scalar > qpp::grams (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

Gram-Schmidt orthogonalization.

std::vector< idx > qpp::n2multiidx (idx n, const std::vector< idx > &dims)

Non-negative integer index to multi-index.

idx qpp::multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

Multi-index to non-negative integer index.

ket qpp::mket (const std::vector< idx > &mask, const std::vector< idx > &dims)

Multi-partite qudit ket.

ket qpp::mket (const std::vector< idx > &mask, idx d=2)

Multi-partite qudit ket.

• cmat qpp::mprj (const std::vector< idx > &mask, const std::vector< idx > &dims)

Projector onto multi-partite qudit ket.

cmat qpp::mprj (const std::vector < idx > &mask, idx d=2)

Projector onto multi-partite qudit ket.

template<typename InputIterator >

std::vector< double > qpp::abssq (InputIterator first, InputIterator last)

Computes the absolute values squared of an STL-like range of complex numbers.

• template<typename Container >

std::vector< double > qpp::abssq (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Computes the absolute values squared of an STL-like container.

template<typename Derived >

```
std::vector< double > qpp::abssq (const Eigen::MatrixBase< Derived > &A)
```

Computes the absolute values squared of an Eigen expression.

template<typename InputIterator >

std::iterator_traits< InputIterator >::value_type qpp::sum (InputIterator first, InputIterator last)

Element-wise sum of an STL-like range.

template<typename Container >

Container::value_type qpp::sum (const Container &c, typename std::enable_if< is_iterable< Container >--:value >::type *=nullptr)

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

std::iterator traits< InputIterator >::value type qpp::prod (InputIterator first, InputIterator last)

Element-wise product of an STL-like range.

• template<typename Container >

Container::value_type qpp::prod (const Container &c, typename std::enable_if< is_iterable< Container > ::value >::type *=nullptr)

Element-wise product of the elements of an STL-like container.

• template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > qpp::rho2pure (const Eigen::MatrixBase< Derived > &A)
```

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

std::vector< idx > qpp::complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

• template<typename Derived >

```
std::vector< double > qpp::rho2bloch (const Eigen::MatrixBase< Derived > &A)
```

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat qpp::bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

template<char... Bits>

```
ket qpp::literals::operator"" _ket ()
```

Multi-partite qubit ket user-defined literal.

template<char... Bits>

```
bra qpp::literals::operator"" _bra ()
```

Multi-partite qubit bra user-defined literal.

template<char... Bits>
 cmat qpp::literals::operator"" _prj ()

Multi-partite qubit projector user-defined literal.

• template<class T >

void qpp::internal::hash_combine (std::size_t &seed, const T &v)

• template<typename Derived >

std::size_t qpp::hash_eigen_expression (const Eigen::MatrixBase< Derived > &A)

Computes the hash of en Eigen matrix/vector/expression.


8.16.1 Detailed Description

Generic quantum computing functions.

8.17 input_output.h File Reference

Input/output functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

- template<typename Derived >
 internal::IOManipEigen qpp::disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
 Eigen expression ostream manipulator.
- internal::IOManipEigen qpp::disp (cplx z, double chop=qpp::chop)

 Complex number ostream manipulator.

template<typename InputIterator >
 internal::IOManipRange< InputIterator > qpp::disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")

Range ostream manipulator.

template<typename Container>
 internal::IOManipRange< typename Container::const_iterator > qpp::disp (const Container &c, const std
 ::string &separator, const std::string &start="[", const std::string &end="]", typename std::enable_if< is_←
 iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

template<typename PointerType >
 internal::IOManipPointer< PointerType > qpp::disp (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")

C-style pointer ostream manipulator.

 $\bullet \ \ \mathsf{template} \mathord{<} \mathsf{typename} \ \mathsf{Derived} >$

void qpp::save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.


8.17.1 Detailed Description

Input/output functions.

8.18 instruments.h File Reference

Measurement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const

Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)

Generalized inner product.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

template<typename Derived >

std::tuple < std::vector < idx >, double, cmat $> qpp::measure_seq$ (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template<typename Derived >
 std::tuple< std::vector< idx >, double, cmat > qpp::measure_seq (const Eigen::MatrixBase< Derived > &A,
 std::vector< idx > target, idx d=2)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.


8.18.1 Detailed Description

Measurement functions.

8.19 internal/classes/iomanip.h File Reference

Input/output manipulators.

This graph shows which files directly or indirectly include this file:



Classes

- class qpp::internal::IOManipRange
 InputIterator >
- class qpp::internal::IOManipPointer
 PointerType >
- class qpp::internal::IOManipEigen

Namespaces

• qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


8.19.1 Detailed Description

Input/output manipulators.

8.20 internal/classes/singleton.h File Reference

Singleton pattern via CRTP.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::internal::Singleton < T >
 Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Namespaces

qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


8.20.1 Detailed Description

Singleton pattern via CRTP.

8.21 internal/util.h File Reference

Internal utility functions.

This graph shows which files directly or indirectly include this file:



Classes

struct qpp::internal::Display_Impl_

Namespaces

• qpp

Quantum++ main namespace.

qpp::internal

Internal utility functions, do not use them directly or modify them.

Functions

- void qpp::internal::n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx qpp::internal::multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- template<typename Derived >
 bool qpp::internal::check_square_mat (const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
 bool qpp::internal::check_vector (const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
 bool qpp::internal::check_rvector (const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
 bool qpp::internal::check_cvector (const Eigen::MatrixBase< Derived > &A)
- template<typename T >
 bool qpp::internal::check_nonzero_size (const T &x) noexcept
- template<typename T1, typename T2 >
 bool qpp::internal::check_matching_sizes (const T1 &lhs, const T2 &rhs) noexcept
- bool qpp::internal::check_dims (const std::vector< idx > &dims)
- template<typename Derived >
 bool qpp::internal::check_dims_match_mat (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
 bool qpp::internal::check_dims_match_cvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- template<typename Derived >
 bool qpp::internal::check_dims_match_rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)
- bool qpp::internal::check_eq_dims (const std::vector< idx > &dims, idx dim) noexcept
- bool qpp::internal::check no duplicates (std::vector < idx > v)
- bool qpp::internal::check_subsys_match_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)
- template<typename Derived >
 bool qpp::internal::check_qubit_matrix (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
 bool qpp::internal::check_qubit_cvector (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
 bool qpp::internal::check_qubit_rvector (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
 bool qpp::internal::check_qubit_vector (const Eigen::MatrixBase< Derived > &A) noexcept
- bool qpp::internal::check_perm (const std::vector< idx > &perm)
- template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::internal::kron2 (const Eigen::MatrixBase< Derived1 > &A,
 const Eigen::MatrixBase< Derived2 > &B)
- template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::internal::dirsum2 (const Eigen::MatrixBase< Derived1 > &A,
 const Eigen::MatrixBase< Derived2 > &B)
- template<typename T >
 void qpp::internal::variadic_vector_emplace (std::vector< T > &)
- template<typename T, typename First, typename... Args>
 void qpp::internal::variadic_vector_emplace (std::vector< T > &v, First &&first, Args &&... args)
- idx qpp::internal::get_num_subsys (idx D, idx d)
- idx qpp::internal::get dim subsys (idx sz, idx N)

8.21.1 Detailed Description

Internal utility functions.

8.22 MATLAB/matlab.h File Reference

Input/output interfacing with MATLAB.

```
#include "mat.h"
#include "mex.h"
```

Namespaces

qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< cplx > ::type
 qpp::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::

Scalar > >::type qpp::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.


8.22.1 Detailed Description

Input/output interfacing with MATLAB.

8.23 number theory.h File Reference

Number theory functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

std::vector< int > qpp::x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double qpp::contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

• bigint qpp::gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint qpp::gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint qpp::lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint qpp::lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > qpp::invperm (const std::vector< idx > &perm)

Inverse permutation.

• std::vector< idx > qpp::compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

• std::vector< bigint > qpp::factors (bigint a)

Prime factor decomposition.

• bigint dpp::modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

• bigint qpp::modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple < bigint, bigint, bigint > qpp::egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint qpp::modinv (bigint a, bigint p)

Modular inverse of a mod p.

• bool qpp::isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

• bigint qpp::randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

• std::vector< std::pair< int, int > > qpp::convergents (const std::vector< int > &cf)

Convergents.

• std::vector< std::pair< int, int > > qpp::convergents (double x, idx N)

Convergents.


8.23.1 Detailed Description

Number theory functions.

8.24 operations.h File Reference

Quantum operation functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 const std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 idx d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const
 Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const
 Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std \leftrightarrow ::vector< idx > &target, const std::vector< idx > &dims)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

• template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std ::vector< idx > &target, idx d=2)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat qpp::kraus2super (const std::vector< cmat > &Ks)

Superoperator matrix.

cmat gpp::kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector< cmat > qpp::choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat qpp::choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat qpp::super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace2 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

• template<typename Derived >

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Partial transpose.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2)

Partial transpose.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &perm, const std::vector< idx > &dims)

Subsystem permutation.

template<typename Derived >

 $dyn_mat < typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &perm, idx d=2)$

Subsystem permutation.

template<typename Derived >
 dyn_mat< typename Derived::Scalar > qpp::applyQFT (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

```
dyn_mat< typename Derived::Scalar > qpp::applyTFQ (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)
```

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > qpp::TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)
```

Inverse (adjoint) qudit quantum Fourier transform.

template<typename Derived >

```
dyn\_col\_vect< typename Derived::Scalar > qpp::QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)
```

Qudit quantum Fourier transform.

8.24.1 Detailed Description

Quantum operation functions.

8.25 qpp.h File Reference

Quantum++ main header file, includes all other necessary headers.

```
#include <algorithm>
#include <cassert>
#include <chrono>
#include <cmath>
#include <complex>
#include <cstdlib>
#include <cstring>
#include <exception>
#include <fstream>
#include <functional>
#include <initializer_list>
#include <iomanip>
#include <iterator>
#include <limits>
#include <memory>
#include <numeric>
#include <ostream>
#include <random>
#include <sstream>
#include <stdexcept>
#include <string>
#include <tuple>
#include <type_traits>
#include <unordered_map>
#include <unordered_set>
#include <utility>
#include <vector>
```

```
#include <Eigen/Dense>
#include <Eigen/SVD>
#include "types.h"
#include "classes/exception.h"
#include "constants.h"
#include "traits.h"
#include "classes/idisplay.h"
#include "internal/util.h"
#include "internal/classes/iomanip.h"
#include "input_output.h"
#include "internal/classes/singleton.h"
#include "classes/random_devices.h"
#include "random.h"
#include "number_theory.h"
#include "functions.h"
#include "classes/init.h"
#include "classes/codes.h"
#include "classes/gates.h"
#include "classes/states.h"
#include "statistics.h"
#include "operations.h"
#include "entropies.h"
#include "entanglement.h"
#include "classes/timer.h"
#include "instruments.h"
#include "classes/reversible.h"
#include "classes/noise.h"
#include "classes/circuits.h"
```

Namespaces

• qpp

Quantum++ main namespace.

Macros

• #define QPP_UNUSED_

8.25.1 Detailed Description

Quantum++ main header file, includes all other necessary headers.

8.25.2 Macro Definition Documentation


8.25.2.1 QPP_UNUSED_

#define QPP_UNUSED_

8.26 random.h File Reference

Randomness-related functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

• double qpp::rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

• bigint qpp::rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx qpp::randidx (idx a=std::numeric_limits < idx >::min(), idx b=std::numeric_limits < idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

Derived qpp::rand (idx rows, idx cols, double a=0, double b=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

template<>

dmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

template<>

cmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

 $\bullet \ \ \text{template}{<} \text{typename Derived} >$

Derived qpp::randn (idx rows, idx cols, double mean=0, double sigma=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

dmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

• template<>

cmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

• double qpp::randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

cmat qpp::randU (idx D=2)

Generates a random unitary matrix.

cmat qpp::randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > qpp::randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat qpp::randH (idx D=2)

Generates a random Hermitian matrix.

ket qpp::randket (idx D=2)

Generates a random normalized ket (pure state vector)

cmat qpp::randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > qpp::randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > qpp::randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.


8.26.1 Detailed Description

Randomness-related functions.

8.27 statistics.h File Reference

Statistics functions.

This graph shows which files directly or indirectly include this file:



8.28 traits.h File Reference 389

Namespaces

• qpp

Quantum++ main namespace.

Functions

std::vector< double > qpp::uniform (idx N)

Uniform probability distribution vector.

std::vector< double > qpp::marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > qpp::marginalY (const dmat &probXY)

Marginal distribution.

• template<typename Container >

double qpp::avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_ \leftarrow iterable< Container >::value >::type *=nullptr)

Average.

 $\bullet \ \ \text{template}{<} \text{typename Container} >$

double qpp::cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Covariance.

• template<typename Container >

double qpp::var (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_ \leftarrow iterable< Container >::value >::type *=nullptr)

Variance.

• template<typename Container >

 $\label{lem:const} \mbox{double qpp::sigma (const std::vector< double > \&prob, const Container \&X, typename std::enable_if< is_{\leftarrow} iterable< Container >::value >::type *=nullptr)$

Standard deviation.

• template<typename Container >

double qpp::cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if is_iterable Container >::value >::type *=nullptr)

Correlation.


8.27.1 Detailed Description

Statistics functions.

8.28 traits.h File Reference

Type traits.

This graph shows which files directly or indirectly include this file:



Classes

```
    struct qpp::make_void < Ts >
        Helper for qpp::to_void <> alias template.
```

struct qpp::is_iterable < T, typename >

Checks whether T is compatible with an STL-like iterable container.

- struct qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(*(std::declval < T >().end()), decltyp
- struct qpp::is_matrix_expression< Derived >

Checks whether the type is an Eigen matrix expression.

struct qpp::is_complex< T >

Checks whether the type is a complex type.

struct qpp::is_complex< std::complex< T >>

Checks whether the type is a complex number type, specialization for complex types.

Namespaces

• qpp

Quantum++ main namespace.

Typedefs

```
    template<typename... Ts>
    using qpp::to_void = typename make_void< Ts... >::type
        Alias template that implements the proposal for void_t.
```


8.28.1 Detailed Description

Type traits.

8.29 types.h File Reference

Type aliases.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Typedefs

• using qpp::idx = std::size_t

Non-negative integer index, make sure you use an unsigned type.

• using qpp::bigint = long long int

Big integer.

• using qpp::cplx = std::complex< double >

Complex number in double precision.

• using qpp::ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector.

• using qpp::bra = Eigen::RowVectorXcd

Complex (double precision) dynamic Eigen row vector.

• using qpp::cmat = Eigen::MatrixXcd

Complex (double precision) dynamic Eigen matrix.

using qpp::dmat = Eigen::MatrixXd

Real (double precision) dynamic Eigen matrix.

 $\bullet \ \ \text{template}{<} \text{typename Scalar} >$

```
using qpp::dyn_mat = Eigen::Matrix< Scalar, Eigen::Dynamic, Eigen::Dynamic >
```

Dynamic Eigen matrix over the field specified by Scalar.

template<typename Scalar >

```
using qpp::dyn_col_vect = Eigen::Matrix < Scalar, Eigen::Dynamic, 1 >
```

Dynamic Eigen column vector over the field specified by Scalar.

template<typename Scalar >

```
using qpp::dyn_row_vect = Eigen::Matrix< Scalar, 1, Eigen::Dynamic >
```

Dynamic Eigen row vector over the field specified by Scalar.

8.29.1 Detailed Description

Type aliases.

8.30 /Users/vlad/qpp/README.md File Reference

Index

/Users/vlad/qpp/README.md, 392	avg
~Codes	qpp, 36
gpp::Codes, 136	۹۲۲, ۵۵
	b00
~Dynamic_bitset	
qpp::Dynamic_bitset, 158	qpp::States, 330
\sim Gates	b01
qpp::Gates, 174	qpp::States, 331
~IDisplay	b10
	qpp::States, 331
qpp::IDisplay, 190	
∼IJSON	b11
qpp::IJSON, 193	qpp::States, 331
~Init	begin
qpp::Init, 195	qpp::QCircuit, 273, 274
~NoiseBase	bigint
qpp::NoiseBase, 242	qpp, 26
~QCircuit	Bit_circuit
qpp::QCircuit, 273	qpp::Bit_circuit, 131
~QEngine	bloch2rho
qpp::QEngine, 297	qpp, 36
~RandomDevices	bra
qpp::RandomDevices, 318	qpp, 26
\sim Singleton	
qpp::internal::Singleton, 322	c_reg_
~States	qpp::QCircuit::MeasureStep, 236
qpp::States, 328	cCTRL_custom
	qpp::QCircuit, 276
~Timer	
qpp::Timer, 339	cCTRL
	qpp::QCircuit, 274–276
A_	CNOTba
qpp::internal::IOManipEigen, 199	qpp::Gates, 183
absm	CNOT
	qpp::Bit_circuit, 131
qpp, 28	
abssq	qpp::Bit_circuit::Gate_count, 170
qpp, 29	qpp::Gates, 183
adjoint	CTRL_custom
qpp, 30	qpp::QCircuit, 279
all	CTRL
	qpp::Gates, 175
qpp::Dynamic_bitset, 158	
anticomm	qpp::QCircuit, 277, 278
qpp, 30	cbegin
any	qpp::QCircuit, 274
qpp::Dynamic_bitset, 158	cend
	qpp::QCircuit, 276
apply	
qpp, 31–33	check_cvector
applyCTRL	qpp::internal, 120
qpp, 33, 34	check_dims
applyQFT	qpp::internal, 120
qpp, 35	check dims match cvect
applyTFQ	qpp::internal, 120
qpp, 35	check_dims_match_mat

qpp::internal, 120	compperm
check_dims_match_rvect	qpp, 38
qpp::internal, 120	compute_probs_
check_eq_dims	qpp::NoiseBase, 242
qpp::internal, 121	compute_state_
check_matching_sizes	qpp::NoiseBase, 242
qpp::internal, 121	concurrence
check_no_duplicates	qpp, 40
qpp::internal, 121	conjugate
check_nonzero_size	qpp, 40
qpp::internal, 121	const_iterator
check_perm	qpp::QCircuit, 271 constants.h, 365
qpp::internal, 121	contfrac2x
check_qubit_cvector	
qpp::internal, 121	qpp, 40 convergents
check_qubit_matrix	qpp, 41
qpp::internal, 122	cor
check_qubit_rvector	qpp, 42
qpp::internal, 122	cosm
check_qubit_vector	qpp, 42
qpp::internal, 122	count
check_rvector	qpp::Dynamic_bitset, 158
qpp::internal, 122	count
check_square_mat	qpp::QCircuit, 292
qpp::internal, 122 check_subsys_match_dims	COV
qpp::internal, 122	qpp, 43
check_vector	cplx
qpp::internal, 123	qpp, 27
choi2kraus	ctrl_
qpp, 36	qpp::QCircuit::GateStep, 187
choi2super	CustomException
qpp, 37	qpp::exception::CustomException, 138
chop	cwise
qpp, 116	qpp, 43
chop_	CZ
qpp::internal::IOManipEigen, 200	qpp::Gates, 183
classes/circuits.h, 355	d_
classes/codes.h, 356	u_ qpp::NoiseBase, 245
classes/exception.h, 357	qpp:://oisebase, 243 qpp::QCircuit, 292
classes/gates.h, 359	data
classes/idisplay.h, 360	qpp::Dynamic_bitset, 158
classes/init.h, 360	depth_
classes/noise.h, 361	qpp::QCircuit, 292
classes/random_devices.h, 362	det
classes/reversible.h, 363	qpp, 44
classes/states.h, 363	difference_type
classes/timer.h, 364	qpp::QCircuit::iterator, 213
cmat	dirsum
qpp, 26	qpp, 44–46
Codes	dirsum2
qpp::Codes, 136	qpp::internal, 123
codeword	dirsumpow
qpp::Codes, 136	qpp, 46
comm	disp
qpp, 37	qpp, 47, 48
complement	display
qpp, 38	qpp::Dynamic_bitset, 159

qpp::IDisplay, 191	qpp::exception::MatrixNotCvector, 222
qpp::QCircuit, 279	qpp::exception::MatrixNotRvector, 224
qpp::QCircuit::iterator::value_type_, 350	qpp::exception::MatrixNotSquare, 226
qpp::QEngine, 297	qpp::exception::MatrixNotSquareNorCvector, 228
qpp::Timer, 339	qpp::exception::MatrixNotSquareNorRvector, 230
qpp::internal::IOManipEigen, 199	
	qpp::exception::MatrixNotSquareNorVector, 232
qpp::internal::IOManipPointer, 202	qpp::exception::MatrixNotVector, 234
qpp::internal::IOManipRange, 205	qpp::exception::NoCodeword, 238
display_impl_	qpp::exception::NotBipartite, 248
qpp::internal::Display_Impl_, 152	qpp::exception::NotImplemented, 250
dits_	qpp::exception::NotQubitCvector, 252
qpp::QEngine, 302	qpp::exception::NotQubitMatrix, 254
dmat	qpp::exception::NotQubitRvector, 256
qpp, <mark>27</mark>	qpp::exception::NotQubitSubsys, 258
dyn_col_vect	qpp::exception::NotQubitVector, 260
qpp, 27	qpp::exception::OutOfRange, 262
dyn_mat	qpp::exception::PermInvalid, 264
qpp, 27	qpp::exception::PermMismatchDims, 266
dyn_row_vect	qpp::exception::QuditAlreadyMeasured, 313
qpp, 27	qpp::exception::SizeMismatch, 324
Dynamic_bitset	qpp::exception::SubsysMismatchDims, 336
qpp::Bit_circuit, 132	qpp::exception::TypeMismatch, 343
qpp::Dynamic bitset, 157	qpp::exception::UndefinedType, 345
qppbynamic_bitset, 137	
ee	qpp::exception::Unknown, 347
qpp, 116	qpp::exception::ZeroSize, 353
egcd	execute
-	qpp::QEngine, 297, 298
qpp, 49	expandout
elg	qpp::Gates, 175, 176
qpp, 49	experimental/experimental.h, 369
elem_	expm
qpp::QCircuit::iterator, 217	qpp, 52
end	
qpp::QCircuit, 279, 280	FRED
end_	qpp::Bit_circuit, 132
qpp::Timer, 341	qpp::Bit_circuit::Gate_count, 171
qpp::internal::IOManipPointer, 202	qpp::Gates, 183
qpp::internal::IOManipRange, 206	factors
entanglement	qpp, 53
qpp, 50	Fd
entanglement.h, 366	qpp::Gates, 177
entropies.h, 368	fill_Ks_
entropy	qpp::QuditDepolarizingNoise, 316
qpp, 51	fill_probs_
evals	qpp::QuditDepolarizingNoise, 316
qpp, 51	
evects	first_
	qpp::internal::IOManipRange, 206
qpp, 52	flip
Exception	qpp::Dynamic_bitset, 159
qpp::exception::DimsInvalid, 141	functions.h, 369
qpp::exception::DimsMismatchCvector, 143	funm
qpp::exception::DimsMismatchMatrix, 145	qpp, 53
qpp::exception::DimsMismatchRvector, 147	
qpp::exception::DimsMismatchVector, 149	GHZ
qpp::exception::DimsNotEqual, 151	qpp::States, 331
qpp::exception::Duplicates, 154	gate
qpp::exception::Exception, 169	qpp::QCircuit, 280, 281
qpp::exception::InvalidIterator, 197	gate_
qpp::exception::MatrixMismatchSubsys, 220	qpp::QCircuit::GateStep, 187
	المعادية الم

gate_count	get_measurement_count
qpp::Bit_circuit, 134	qpp::QCircuit, 285
gate_custom	get_measurements_
qpp::QCircuit, 281	qpp::QCircuit, 286
gate_fan	get_name
qpp::QCircuit, 282, 283	qpp::Gates, 178
gate_type_	qpp::QCircuit, 286
qpp::QCircuit::GateStep, 187	get_nc
GateStep	qpp::QCircuit, 286
qpp::QCircuit::GateStep, 186	get_non_measured
GateType	qpp::QCircuit, 286
qpp::QCircuit, 271	get_not_measured
Gates	qpp::QEngine, 299
qpp::Gates, 174	get_nq
gates_	qpp::QCircuit, 287
qpp::QCircuit, 292	get_num_subsys
gates_ip_	qpp::internal, 123
qpp::QCircuit::iterator::value_type_, 350	get_prng
gcd	qpp::RandomDevices, 319
qpp, 54	get_probs
gconcurrence	qpp::NoiseBase, 244
qpp, 54	qpp::QEngine, 299
generated	get_psi
qpp::NoiseBase, 245	qpp::QEngine, 300
get	get_ref_psi
qpp::Dynamic_bitset, 160	qpp::QEngine, 300
get_Ks	get_relative_pos_
qpp::NoiseBase, 243	qpp::QEngine, 300
get_circuit	get_step_count
qpp::QEngine, 298	qpp::QCircuit, 287
get d	get_thread_local_instance
qpp::NoiseBase, 243	qpp::internal::Singleton, 322
qpp::QCircuit, 283	grams
get_dim_subsys	qpp, 55, 56
qpp::internal, 123	11
get_dit	H
qpp::QEngine, 298	qpp::Gates, 183
get_dits	hash_combine
qpp::QEngine, 298	qpp::internal, 123
get_duration	hash_eigen_expression
qpp::Timer, 340	qpp, 56
get_gate_count	heig
qpp::QCircuit, 283	qpp, 57 hevals
get_gate_depth	
qpp::QCircuit, 284	qpp, 57
get_gates_	hevects
qpp::QCircuit, 284	qpp, 57
get instance	i
qpp::internal::Singleton, 322	qpp::NoiseBase, 245
get_last_idx	IDisplay
qpp::NoiseBase, 243	qpp::IDisplay, 190
get_last_K	IJSON
qpp::NoiseBase, 244	qpp::IJSON, 192, 193
get last p	IOManipEigen
qpp::NoiseBase, 244	qpp::internal::IOManipEigen, 199
get_measured	IOManipPointer
qpp::QCircuit, 284, 285	qpp::internal::IOManipPointer, 201, 202
qpp::QEngine, 299	IOManipRange

ld	qpp::internal::IOManipRange, 205	qpp::NoiseBase, 246
	qpp::Gates, 178	last_ qpp::internal::IOManipRange, 206
ld2	qpp::Gates, 184	lcm
idx	qpp, 28	qpp, 63, 64 load
inde	X_	qpp, 64
infty	qpp::Dynamic_bitset, 160	qpp::RandomDevices, 319 loadMATLAB
Init	qpp, 116	qpp, 65, 66 logdet
Init	qpp::Init, 195	qpp, 66
inpu	t_output.h, 374	logm
	uments.h, 375	qpp, 67
	nal/classes/iomanip.h, 377	lognegativity
inter	nal/classes/singleton.h, 378	qpp, 67
inter	nal/util.h, 378	MATIAR/ HILL COS
inter	nal::Singleton < const Codes >	MATLAB/matlab.h, 380
	qpp::Codes, 137	MODMUL 170
inter	nal::Singleton< const Gates >	qpp::Gates, 178
	qpp::Gates, 183	marginalX
inter	nal::Singleton< const Init >	qpp, 68 marginalY
	qpp::Init, 195	qpp, 68
inter	nal::Singleton < const States >	mats
	qpp::States, 330	qpp::QCircuit::MeasureStep, 236
inter	nal::Singleton < RandomDevices >	maxn
	qpp::RandomDevices, 320	qpp, 116
inve		measure
invo	qpp, 58	qpp, 69–73
invp	qpp, 58	measure_seq
ip	ч рр, 30	qpp, 74
ıρ	qpp, 59	MeasureStep
ip_	Ч рр, оо	qpp::QCircuit::MeasureStep, 236
·P_	qpp::QCircuit::iterator::value_type_, 350	MeasureType
ispri		qpp::QCircuit, 272
	qpp, 60	measured_
itera		qpp::QCircuit, 292
	qpp::QCircuit::iterator, 214	measurement_count_
itera	tor_category	qpp::QCircuit, 292
	qpp::QCircuit::iterator, 213	measurement_type_ qpp::QCircuit::MeasureStep, 236
jn		measurements_
,	qpp::States, 328	qpp::QCircuit, 293
		measurements_ip_
ket		<pre>qpp::QCircuit::iterator::value_type_, 351</pre>
	qpp, 28	measureV
krau	s2choi	qpp::QCircuit, 287, 288
	qpp, 60	measureZ
krau	s2super	qpp::QCircuit, 288
	qpp, 61	mes
kron		qpp::States, 328
1	qpp, 61, 62	minus
kron		qpp::States, 329
le== :-	qpp::internal, 123	mket
kron	•	qpp, 75, 76
K۵	qpp, 63	modiny
Ks_		qpp, 76

modmul	qpp::NoiseBase, 244, 245
qpp, 77	qpp::internal::HashEigen, 188
modpow	qpp::internal::KeyEqualEigen, 218
qpp, 77	operator++
mprj	qpp::QCircuit::iterator, 215
qpp, 78	operator-
msg	qpp::Dynamic_bitset, 161
qpp::exception::Exception, 170	operator=
multiidx2n	qpp::IDisplay, 191
qpp, 79	qpp::IJSON, 193
qpp::internal, 124	qpp::QCircuit::iterator, 215
	qpp::QCircuit::iterator::value_type_, 350
n2multiidx	qpp::QEngine, 301
qpp, 79	qpp::Timer, 340
qpp::internal, 124	qpp::internal::IOManipPointer, 202
N_	qpp::internal::IOManipRange, 205
qpp::Dynamic_bitset, 165	qpp::internal::Singleton, 322
qpp::internal::IOManipPointer, 203	operator==
NOT	qpp::Dynamic_bitset, 162
qpp::Bit_circuit, 132	qpp::QCircuit::iterator, 216
qpp::Bit_circuit::Gate_count, 171	operator"" _bra
name	
qpp::QCircuit, 293	qpp::literals, 125
qpp::QCircuit::GateStep, 187	operator""_i
qpp::QCircuit::MeasureStep, 237	qpp, 82
* * * * * * * * * * * * * * * * * * * *	qpp::literals, 125
nc_	operator"" _ket
qpp::QCircuit, 293	qpp::literals, 126
negativity	operator"" _prj
qpp, 80	qpp::literals, 126
noise_type	
mmuNainaDana 044	n
qpp::NoiseBase, 241	p_ apprinternal::IOManipPointer 202
NoiseBase	qpp::internal::IOManipPointer, 203
NoiseBase qpp::NoiseBase, 241	qpp::internal::IOManipPointer, 203 pGHZ
NoiseBase qpp::NoiseBase, 241 none	qpp::internal::IOManipPointer, 203 pGHZ qpp::States, 332
NoiseBase qpp::NoiseBase, 241 none qpp::Dynamic_bitset, 160	qpp::internal::IOManipPointer, 203 pGHZ qpp::States, 332 pb00
NoiseBase qpp::NoiseBase, 241 none qpp::Dynamic_bitset, 160 norm	qpp::internal::IOManipPointer, 203 pGHZ qpp::States, 332 pb00 qpp::States, 331
NoiseBase	qpp::internal::IOManipPointer, 203 pGHZ qpp::States, 332 pb00 qpp::States, 331 pb01
NoiseBase	qpp::internal::IOManipPointer, 203 pGHZ qpp::States, 332 pb00 qpp::States, 331 pb01 qpp::States, 331
NoiseBase	qpp::internal::IOManipPointer, 203 pGHZ qpp::States, 332 pb00 qpp::States, 331 pb01 qpp::States, 331 pb10
NoiseBase	qpp::internal::IOManipPointer, 203 pGHZ qpp::States, 332 pb00 qpp::States, 331 pb01 qpp::States, 331 pb10 qpp::States, 332
NoiseBase	qpp::internal::IOManipPointer, 203 pGHZ qpp::States, 332 pb00 qpp::States, 331 pb01 qpp::States, 331 pb10 qpp::States, 332 pb11
NoiseBase	qpp::internal::IOManipPointer, 203 pGHZ qpp::States, 332 pb00 qpp::States, 331 pb01 qpp::States, 331 pb10 qpp::States, 332 pb11 qpp::States, 332
NoiseBase	qpp::internal::IOManipPointer, 203 pGHZ qpp::States, 332 pb00 qpp::States, 331 pb01 qpp::States, 331 pb10 qpp::States, 332 pb11 qpp::States, 332 pb11
NoiseBase	qpp::internal::IOManipPointer, 203 pGHZ qpp::States, 332 pb00 qpp::States, 331 pb01 qpp::States, 331 pb10 qpp::States, 332 pb11 qpp::States, 332 pi qpp, 116
NoiseBase	qpp::internal::IOManipPointer, 203 pGHZ qpp::States, 332 pb00 qpp::States, 331 pb01 qpp::States, 331 pb10 qpp::States, 332 pb11 qpp::States, 332 pi qpp, 116 plus
NoiseBase	qpp::internal::IOManipPointer, 203 pGHZ qpp::States, 332 pb00 qpp::States, 331 pb01 qpp::States, 331 pb10 qpp::States, 332 pb11 qpp::States, 332 pb11 qpp::States, 332 pi qpp, 116 plus qpp::States, 329
NoiseBase	qpp::internal::IOManipPointer, 203 pGHZ qpp::States, 332 pb00 qpp::States, 331 pb01 qpp::States, 331 pb10 qpp::States, 332 pb11 qpp::States, 332 pb11 qpp::States, 332 pi qpp, 116 plus qpp::States, 329 pointer
NoiseBase	qpp::internal::IOManipPointer, 203 pGHZ qpp::States, 332 pb00 qpp::States, 331 pb01 qpp::States, 331 pb10 qpp::States, 332 pb11 qpp::States, 332 pb11 qpp::States, 332 pi qpp, 116 plus qpp::States, 329
NoiseBase	qpp::internal::IOManipPointer, 203 pGHZ qpp::States, 332 pb00 qpp::States, 331 pb01 qpp::States, 331 pb10 qpp::States, 332 pb11 qpp::States, 332 pb11 qpp::States, 332 pi qpp, 116 plus qpp::States, 329 pointer
NoiseBase	qpp::internal::IOManipPointer, 203 pGHZ qpp::States, 332 pb00 qpp::States, 331 pb01 qpp::States, 331 pb10 qpp::States, 332 pb11 qpp::States, 332 pb11 qpp::States, 332 pi qpp, 116 plus qpp::States, 329 pointer qpp::QCircuit::iterator, 213
NoiseBase	qpp::internal::IOManipPointer, 203 pGHZ qpp::States, 332 pb00 qpp::States, 331 pb01 qpp::States, 331 pb10 qpp::States, 332 pb11 qpp::States, 332 pb11 qpp::States, 332 pi qpp, 116 plus qpp::States, 329 pointer qpp::QCircuit::iterator, 213 powm
NoiseBase	qpp::internal::IOManipPointer, 203 pGHZ qpp::States, 332 pb00 qpp::States, 331 pb01 qpp::States, 331 pb10 qpp::States, 332 pb11 qpp::States, 332 pi qpp, 116 plus qpp::States, 329 pointer qpp::QCircuit::iterator, 213 powm qpp, 82
NoiseBase	qpp::internal::IOManipPointer, 203 pGHZ qpp::States, 332 pb00 qpp::States, 331 pb01 qpp::States, 331 pb10 qpp::States, 332 pb11 qpp::States, 332 pi qpp, 116 plus qpp::States, 329 pointer qpp::QCircuit::iterator, 213 powm qpp, 82 prj
NoiseBase	qpp::internal::IOManipPointer, 203 pGHZ qpp::States, 332 pb00 qpp::States, 331 pb01 qpp::States, 331 pb10 qpp::States, 332 pb11 qpp::States, 332 pi qpp, 116 plus qpp::States, 329 pointer qpp::QCircuit::iterator, 213 powm qpp, 82 prj qpp, 82
NoiseBase	qpp::internal::IOManipPointer, 203 pGHZ qpp::States, 332 pb00 qpp::States, 331 pb01 qpp::States, 331 pb10 qpp::States, 332 pb11 qpp::States, 332 pi qpp, 116 plus qpp::States, 329 pointer qpp::QCircuit::iterator, 213 powm qpp, 82 prij qpp, 82 prig_ qpp::RandomDevices, 320 probs_
NoiseBase	qpp::internal::IOManipPointer, 203 pGHZ qpp::States, 332 pb00 qpp::States, 331 pb01 qpp::States, 331 pb10 qpp::States, 332 pb11 qpp::States, 332 pi qpp, 116 plus qpp::States, 329 pointer qpp::QCircuit::iterator, 213 powm qpp, 82 prj qpp, 82 prig qpp::RandomDevices, 320 probs_ qpp::NoiseBase, 246
NoiseBase	qpp::internal::IOManipPointer, 203 pGHZ qpp::States, 332 pb00 qpp::States, 331 pb01 qpp::States, 331 pb10 qpp::States, 332 pb11 qpp::States, 332 pi qpp, 116 plus qpp::States, 329 pointer qpp::QCircuit::iterator, 213 powm qpp, 82 prij qpp, 82 prig_ qpp::RandomDevices, 320 probs_
NoiseBase	qpp::internal::IOManipPointer, 203 pGHZ qpp::States, 332 pb00 qpp::States, 331 pb01 qpp::States, 331 pb10 qpp::States, 332 pb11 qpp::States, 332 pi qpp, 116 plus qpp::States, 329 pointer qpp::QCircuit::iterator, 213 powm qpp, 82 prj qpp, 82 prig qpp::RandomDevices, 320 probs_ qpp::NoiseBase, 246
NoiseBase	qpp::internal::IOManipPointer, 203 pGHZ

psi_ qpp::CEngine, 302 ptrace		
ptrace conjugate, 40 ptrace1 contrac2x, 40 qpp, 85, 86 cor, 42 ptrace2 cosm, 42 qpp, 86, 87 cov, 43 ptranspose cpk, 27 qpp, 87, 88 cwise, 43 pw det, 44 qpp::States, 332 dirsum, 44–46 px1 dirsum, 44–46 qpp::States, 332 dyn, col_vect, 27 py dyn_col_vect, 27 qpp::States, 333 ego, 47, 48 pt dyn_col_vect, 27 qpp::States, 333 egod, 49 pc egod, 49 ejc, 49 epr::States, 333 pp::States, 333 entanglement, 50 pt epp::States, 333 pp::Gircuit, 273 expr. 52 qpp::States, 333 entanglement, 50 pt epp::Gircuit, 273 QEngine factors, 53 qpp::Circuit, 281 grams, 55, 56 QPp::QCircuit, 291 grams, 55, 56 qpp::QCircuit::sterator, 217 grams, 55, 56 qpp::QCircuit::		
qpp, 84, 85 contrac2x, 40 ptrace2 cor, 42 qpp, 85, 86 cor, 42 qpp, 86, 87 cov, 43 ptrace2 cow, 42 qpp, 87, 88 cwise, 43 pW det, 44 qpp::States, 332 dirsum, 44–46 px0 dirsumpow, 46 dirsumpow, 46 dirsumpow, 46 qpp::States, 332 dyn_col_vect, 27 pt dyn_col_vect, 27 qpp::States, 333 dyn_col_vect, 27 py1 qpp::States, 333 dyn_col_vect, 27 pp1 qpp::States, 333 egdd, 49 pc2 qpp::States, 333 egdd, 49 pp1 qpp::States, 333 evals, 51 pcrutiout evects, 52 qpp::States, 333 evals, 51 pcrutiout epc.d, 49 pp2 qpp::States, 333 evals, 51 pcrutiout epc.d, 49 qpp::States, 333 eyn.m, 52 qpp::States, 333 eyn.m, 52 qpp::States, 333 eyn.m, 52	"	
ptrace1	•	
qpp, 85, 86 cor, 42 ptrace2 cosm, 42 qpp, 86, 87 cox, 43 ptranspose qpk, 27 qpp, 87, 88 cwise, 43 pW det, 44 qpp::States, 332 dirsumpow, 46 disumpow, 46 disumpow, 47, 48 px1 dmat, 27 qpp::States, 332 dyn_col_vect, 27 py0 qpp::States, 333 dyn_row_vect, 27 py1 ee, 116 egd, 49 qpp::States, 333 egd, 49 egd, 49 pc0 eig, 49 entranglement, 50 pp::Qstates, 333 entranglement, 50 entranglement, 50 pp::Qstates, 333 entranglement, 50 entranglement, 50 pc1 qpp::States, 333 entranglement, 50 pc2 epp::Qstates, 333 entranglement, 50 pc1 qpp::States, 333 entranglement, 50 pc2 expm, 52 expm, 52 det, 28 expm, 52 expm, 52 Qpp::QcCircuit, 273 factors, 53 funm, 53 qp	• •	contfrac2x, 40
ptrace2 cosm, 42 qpp, 86, 87 cov, 43 ptranspose qpp, 87, 88 pW det, 44 qpp:States, 332 dirsum, 44–46 px0 dirsumpow, 46 disp, 47, 48 disp, 47, 48 dmat, 27 dyn_col_vect, 27 py0 dyn_col_vect, 27 qpp:States, 333 dyn_row_vect, 27 py1 ee, 116 qpp:States, 333 eya, 49 pc0 ejg, 49 qpp:States, 333 entanglement, 50 pp1 app:States, 333 evals, 51 QCircuit evects, 52 expm, 52 Qcircuit evects, 52 expm, 52 Qcircuit qpp:Qcircuit, 273 expm, 52 Qcenjine, 296 gcd, 54 gcd, 54 QFT gconcurrence, 54 grams, 55, 56 qpp:Qcircuit; 288 heig, 57 heig, 57 qpp, 88 qpp:Qcircuit; iterator, 217 idx, 28 infty, 116 qpp:Qcircuit; iterator, 217 idx, 28 infty, 116 q	•	_
qpp, 86, 87 cov, 43 ptranspose cplx, 27 qpp, 87, 88 cwise, 43 pW det, 44 qpp::States, 332 dirsum, 44–46 px0 dirsumpow, 46 qpp::States, 332 disp, 47, 48 px1 dmt, 27 qpp::States, 333 dyn_col_vect, 27 qpp::Qpp::States, 333 egcd, 49 p0 egcd, 49 qpp::States, 333 enlanglement, 50 pp::Qpp::States, 333 enlanglement, 50 pp::Qcircuit, 273 exects, 52 qpp::Qcircuit, 273 exects, 52 qpp::Qcircuit, 291 gcd, 54 qpp::Qcircuit, 291 gcd, 54 qpp::Qcircuit, 298 gcd, 54 QPP_UNUSED_ gcd, 54 qpp, 88 qpp::Qricuit::terator, 217 gcd, 54 qpp, 80 heig, 57 qpp, 80 heig, 57 qpp, 80 in/ty, 116 qpp, 89 in/ty, 116 qpp, 89 ipp, 59 absm, 28 jpp, 59 absm, 2		cor, 42
ptranspose cplx, 27 qpp, 87, 88 cwise, 43 pW det, 44 qpp::States, 332 dirsum, 44–46 px0 dirsum, 44–46 qpp::States, 332 dip, 47, 48 px1 dmat, 27 qpp::States, 333 dyn_col_vect, 27 py1 ee, 116 qpp::States, 333 egcd, 49 eig, 49 eig, 49 qpp::States, 333 egcd, 49 eig, 49 entropy, 51 evecls, 52 eye, 52 Gengine entropy, 51 expp::Clircuit, 273 expr. 52 CEngine factors, 53 furm, 53 gcd, 54 QP::Clircuit, 291 gcd, 54 QPT gcd, 54 QPT. UNUSED_ pgcn. 296 QP-UNUSED_ heig, 57 qpp::QEngine, 296 heig, 57 QP_UNUSED_ heig, 57 qpp::QEngine, 303 infty, 116 qpp::QEngine, 303 infty, 116 qpp::QEngine, 303 inverse, 58	•	cosm, 42
qpp, 87, 88 pW	qpp, 86, 87	cov, 43
pW	ptranspose	cplx, 27
qpp::States, 332	qpp, 87, 88	cwise, 43
px0	pW	det, 44
qpp::States, 332	qpp::States, 332	dirsum, 44-46
px1	px0	dirsumpow, 46
px1	qpp::States, 332	disp, 47, 48
qpp::States, 332 py0 qpp::States, 333 py1 qpp::States, 333 pz0 qpp::States, 333 pz1 qpp::States, 333 qpp::Qcircuit, 273 Qcircuit qpp::Qcircuit, 273 qpp::Qcircuit, 291 qpp::Qcircuit, 291 qpp::Qcircuit, 296 qpp. 88 qpp::Qcircuit, 288 QPP_UNUSED qpp.h, 386 qpp.;Qcircuit:iterator, 217 qpp::Qcircuit:iterator, 217 qpp::Qcircuit, 288 qpp::Qcircuit, 288 qpp::Qcircuit, 288 qpp::Qcircuit, 291 qpc::Qcircuit,	px1	•
py0 qpp::States, 333	qpp::States, 332	
qpp::States, 333 py1 qpp::States, 333 pz0 qpp::States, 333 pz1 qpp::States, 333 qpp::States, 333 qpp::States, 333 qpp::States, 333 qpp::States, 333 qpp::Coircuit qpp::States, 333 qpp::Qcircuit, 273 qpp::Qcircuit, 273 qpp::Qcircuit, 291 qpp::Qcircuit, 291 qpp::Qcircuit, 296 qpp::Qcircuit, 288 qpp::Qcircuit, 288 qpp::Qcircuit, 288 qpp::Qcircuit:iterator, 217 qpp::Qcircuit, 288 qpp::Qcircuit, 288 qpp::Qcircuit, 298 qpp::Qcir	py0	
py1	qpp::States, 333	•
qpp::States, 333	py1	- — —
pz0 qpp::States, 333 pz1 qpp::States, 333 entanglement, 50 entropy, 51 entropy, 51 evects, 52 expm, 52 qpp::QCircuit, 273 QEngine qpp::QEngine, 296 QFT qpp, 88 qpp::QCircuit, 288 QPP_UNUSED_ qpp, Na86 qpp::QCircuit:iterator, 217 qpp:, 386 qpp::QCircuit:iterator, 217 qpp::QEngine, 303 qmutualinfo qpp, 89 qpp, 13 absm, 28 absq, 29 adjoint, 30 anticomm, 30 apply, 31–33 applyCFT, 35 applyTFQ, 35 avg, 36 bigint, 26 bloch2rho, 36 bria, 26 choi2kraus, 36 choi2super, 37 chop, 116 cmat, 26 comm, 37 measure, 69–73 measure, 59–73 measure, 59 complement, 50 extable entropy, 51 evals, 51 expm, 52 expm,		
qpp::States, 333 pz1 qpp::States, 333 entanglement, 50 entropy, 51 evals, 51 evals, 51 evects, 52 expm, 52 factors, 53 funm, 53 qpp::QCircuit, 291 qpp::QEngine, 296 QFT qpp, 88 qpp::QCircuit, 288 QPP_UNUSED qpp.h, 386 qc_ qpp::QCircuit::iterator, 217 qpp::QEngine, 303 qmutualinfo qpp, 89 qpp, 13 absm, 28 absa, 29 adjoint, 30 anticomm, 30 apply, 31–33 applyCTRL, 33, 34 applyCTRL, 33, 34 applyTFQ, 35 avg, 36 bigint, 26 bloch2rho, 36 bora, 26 choi2kraus, 36 choi2super, 37 chop, 116 cmat, 26 comm, 37 measure_seq, 74	pz0	•
pz1	•	
qpp::States, 333 QCircuit qpp::QCircuit, 273 QEngine qpp::QCircuit, 291 qpp::QEngine, 296 QFT qpp, 88 qpp::QCircuit, 288 QPP_UNUSED qpp.h, 386 QPP_UNUSED qpp.h, 386 qpp::QCircuit::iterator, 217 qpp::QEngine, 303 qmutualinfo qpp, 89 qpp, 13 absm, 28 abseq, 29 adjoint, 30 anticomm, 30 anticomm, 30 apply, 31–33 applyCTRL, 33, 34 applyCTR, 35 applyTFQ, 35 abpl, 26 bloch2rho, 36 bigint, 26 bloch2rho, 36 bigint, 26 choi2kyaper, 37 chop, 116 cmat, 26 comm, 37 measure_seq, 74		-
QCircuit evets, 52 expm, 52 factors, 53 funm, 53 gcd, 54 gcp;:QCircuit, 291 gcd, 54 gconcurrence, 54 grams, 55, 56 hash_eigen_expression, 56 heig, 57 qpp::QCircuit:iterator, 217 qpp::QEngine, 303 ipp, 59 qpp, 13 absm, 28 abssm, 28 abssm, 29 adjoint, 30 anticomm, 30 apply, 31–33 applyCTRL, 33, 34 applyCTR, 35 applyTFQ, 35 avg, 36 bigint, 26 bloch2rho, 36 bra, 26 choi2kraus, 36 choi2super, 37 chop, 116 cmat, 26 comm, 37 measure_seq, 74	•	• •
qpp::QCircuit, 273 QEngine qpp::QCircuit, 291 qpp::QEngine, 296 QFT qpp, 88 qpp::QCircuit, 288 QPP_UNUSED_ qpp.; 386 qpp::QCircuit:iterator, 217 qpp.; 386 qpp::QCircuit:iterator, 217 qpp::QEngine, 303 qmutualinfo qpp, 89 qpp, 13 absm, 28 abssq, 29 adjoint, 30 anticomm, 30 anticomm, 30 anticomm, 30 apply, 31–33 applyCFRL, 33, 34 applyCFRL, 33, 34 applyCFR, 35 avg, 36 bigint, 26 bloch2rho, 36 bra, 26 choi2kraus, 36 choi2super, 37 chop, 116 cmat, 26 comm, 37 measure_seq, 74	" 1	
QEngine	QCircuit	
QET funm, 53 qpp::QEngine, 296 gcd, 54 QFT gconcurrence, 54 qpp, 88 qpsms, 55, 56 qpp::QCircuit, 288 hash_eigen_expression, 56 QPP_UNUSED_ heig, 57 qpp.h, 386 heveds, 57 qc_ idx, 28 qpp::QCircuit::iterator, 217 idx, 28 qpp::QEngine, 303 infty, 116 qmutualinfo inverse, 58 qpp, 89 inpp; 59 qpp, 13 ip, 59 absm, 28 ket, 28 abssq, 29 ket, 28 adjoint, 30 kraus2choi, 60 anticomm, 30 kraus2super, 61 apply, 31–33 kron, 61, 62 applyGFTL, 33, 34 kronpow, 63 applyGFT, 35 load, 64 avg, 36 loadMATLAB, 65, 66 bigint, 26 logdet, 66 bloch2rho, 36 logm, 67 bra, 26 lognegativity, 67 choi2super, 37 marginalY, 68 choi2super, 37 measure, 69–73 measure, 59–73<	qpp::QCircuit, 273	•
qpp::QEngine, 296 QFT qpp, 88 qpp::QCircuit, 288 QPP_UNUSED_ qpp.h, 386 qp::QCircuit:iterator, 217 qpp.:QEngine, 303 qmutualinfo qpp, 89 qpp, 13 absm, 28 abssq, 29 adjoint, 30 anticomm, 30 anticomm, 30 apply, 31–33 applyCTRL, 33, 34 applyCFT, 35 applyTFQ, 35 avg, 36 bigint, 26 bloch2rho, 36 bra, 26 choi2super, 37 chop, 116 cmat, 26 comm, 37 gcd, 54 gconcurrence, 54 grams, 55, 56 hash_eigen_expression, 56 heig, 57 hevals, 57 hevals, 57 hevals, 57 hevals, 57 infty, 116 inverse, 58 invperm, 58 ipp, 59 isprime, 60 ket, 28 ket, 28 kraus2choi, 60 kraus2super, 61 kron, 61, 62 kronpow, 63 load, 64 loadMATLAB, 65, 66 logdet, 66 logdet, 66 logdet, 66 lognegativity, 67 marginalX, 68 marginalX, 68 maxn, 116 cmax, 26 comm, 37 measure_seq, 74	QEngine	
QFT	qpp::QCircuit, 291	
qpp, 88	qpp::QEngine, 296	-
qpp::QCircuit, 288 QPP_UNUSED_ qpp.h, 386 qc_ qpp::QCircuit::iterator, 217 qpp::QEngine, 303 qmutualinfo qpp, 89 qpp, 13 absm, 28 abssq, 29 adjoint, 30 anticomm, 30 anticomm, 30 apply, 31–33 applyCTRL, 33, 34 applyCTRL, 33, 34 applyFTQ, 35 abigin, 26 bloch2rho, 36 bigint, 26 bloch2rho, 36 bra, 26 choi2kraus, 36 choi2kraus, 36 choi2super, 37 chop, 116 cmat, 26 comm, 37 hash_eigen_expression, 56 heig, 57 hevels, 57 hevels, 57 idx, 28 heig, 57 hevels, 57 hevels, 57 idx, 28 heig, 57 hevels, 57 hevels	QFT	•
QPP_UNUSED_	qpp, 88	_
qpp.h, 386 qc_	qpp::QCircuit, 288	
qp::N, soo qc_ qpp::Qcircuit::iterator, 217 qpp::QEngine, 303 qmutualinfo inverse, 58 qpp, 89 qpp, 13 absm, 28 absm, 28 adjoint, 30 anticomm, 30 anticomm, 30 apply, 31–33 applyCTRL, 33, 34 applyGFT, 35 applyTFQ, 35 abigint, 26 bloch2rho, 36 bigint, 26 bloch2rho, 36 bra, 26 choi2super, 37 chop, 116 cmat, 26 comm, 37 here index as infection infect, 57 idx, 28 idx, 28 infty, 116 inverse, 58 invperm, 58 ipv, 59 invperm, 58 isprime, 60 ket, 28 ket, 28 ket, 28 ket, 28 kraus2choi, 60 kraus2super, 61 kron, 61, 62 kronpow, 63 lom, 63, 64 load, 64 load, 64 loadMATLAB, 65, 66 logdet, 66 logdet, 66 lognegativity, 67 marginalX, 68 marginalY, 68 measure, 69–73 measure_seq, 74	QPP_UNUSED_	C.
qpp::QCircuit::iterator, 217 idx, 28 qpp::QEngine, 303 infty, 116 qmutualinfo inverse, 58 qpp, 89 invperm, 58 qpp, 13 ip, 59 absm, 28 isprime, 60 abssq, 29 ket, 28 adjoint, 30 kraus2choi, 60 anticomm, 30 kraus2super, 61 apply, 31–33 kron, 61, 62 applyCTRL, 33, 34 kronpow, 63 applyGFT, 35 lom, 63, 64 applyTFQ, 35 load, 64 avg, 36 loadMATLAB, 65, 66 bigint, 26 logdet, 66 bloch2rho, 36 logm, 67 bra, 26 lognegativity, 67 choi2kraus, 36 marginalX, 68 choi2super, 37 marginalY, 68 chop, 116 maxn, 116 cmat, 26 measure, 69–73 comm, 37 measure_seq, 74	qpp.h, 386	
qpp::QCircuit::iterator, 217 idx, 28 qpp::QEngine, 303 infty, 116 qmutualinfo inverse, 58 qpp, 89 invperm, 58 qpp, 13 ip, 59 absm, 28 isprime, 60 abssq, 29 ket, 28 adjoint, 30 kraus2choi, 60 anticomm, 30 kraus2super, 61 apply, 31–33 kron, 61, 62 applyCTRL, 33, 34 kronpow, 63 applyTFQ, 35 load, 64 avg, 36 loadMATLAB, 65, 66 bigint, 26 logdet, 66 bloch2rho, 36 logm, 67 bra, 26 lognegativity, 67 choi2kraus, 36 marginalX, 68 choi2super, 37 marginalY, 68 chop, 116 maxn, 116 cmat, 26 measure, 69–73 comm, 37 measure_seq, 74	qc_	
qmutualinfo qpp, 89 invperm, 58 invperm, 58 ipp, 59 isprime, 60 ket, 28 ket, 28 adjoint, 30 kraus2choi, 60 kraus2super, 61 apply, 31–33 kron, 61, 62 applyCTRL, 33, 34 applyQFT, 35 lcm, 63, 64 applyTFQ, 35 avg, 36 bigint, 26 bloch2rho, 36 bloch2rho, 36 choi2super, 37 chop, 116 cmat, 26 comm, 37 invperm isprime invperm, 58 invperm, 58 invperm, 59 invperm, 59 invperm, 58 invperm, 58 invperm, 59 invperm, 59 invperm, 58 invperm, 59 invperm, 59 invperm, 58 invperm, 60 ket, 28 kraus2choi, 60 ket, 28 kraus2choi, 60 kraus2super, 61 kraus2super, 61 kraus2super, 61 kronpow, 63 invperm, 64 invpermental invpermental invperm, 64 invpermental invperm, 64 invpermental invperm, 58 invperm, 58 invperm, 58 invperm, 59 invperm, 58 invperm, 58 invpermental invperm, 58 invperm, 58 invperm, 58 invpermental invperm, 58 invperm, 58 invperm, 58 invperm, 58 invpermental invperm, 58 invperm, 58 invpermental invpermenta		idx, 28
qpp, 89 qpp, 13 absm, 28 abssq, 29 adjoint, 30 anticomm, 30 anticomm, 30 apply, 31–33 applyCTRL, 33, 34 applyTFQ, 35 applyTFQ, 35 avg, 36 bigint, 26 bloch2rho, 36 bra, 26 choi2super, 37 chop, 116 cmat, 26 comm, 37 invperm, 58 ip, 59 isprime, 60 ket, 28 kraus2choi, 60 kraus2super, 61 kron, 61, 62 kronpow, 63 lcm, 63, 64 load, 64 load, 64 logdet, 66 logdet, 66 logm, 67 lognegativity, 67 marginalX, 68 choi2super, 37 marginalY, 68 measure, 69–73 comm, 37 measure_seq, 74	qpp::QEngine, 303	infty, 116
qpp, 13 absm, 28 abssq, 29 adjoint, 30 anticomm, 30 apply, 31–33 applyCTRL, 33, 34 applyQFT, 35 applyTFQ, 35 applyTFQ, 35 abignit, 26 bloch2rho, 36 bloch2rho, 36 choi2super, 37 chop, 116 cmat, 26 comm, 37 isprime, 60 ket, 28 kkraus2choi, 60 kraus2super, 61 kkron, 61, 62 kkronpow, 63 lcm, 63, 64 load, 64 load, 64 loadMATLAB, 65, 66 logdet, 66 lognegativity, 67 marginalX, 68 marginalX, 68 marginalY, 68 maxn, 116 cmat, 26 comm, 37 measure_seq, 74	qmutualinfo	inverse, 58
qpp, 13 ip, 59 absm, 28 isprime, 60 abssq, 29 ket, 28 adjoint, 30 kraus2choi, 60 anticomm, 30 kraus2super, 61 apply, 31–33 kron, 61, 62 applyCTRL, 33, 34 kronpow, 63 applyTFQ, 35 lcm, 63, 64 avg, 36 loadMATLAB, 65, 66 bigint, 26 logdet, 66 bloch2rho, 36 logm, 67 bra, 26 lognegativity, 67 choi2kraus, 36 marginalX, 68 choi2super, 37 marginalY, 68 chop, 116 maxn, 116 cmat, 26 measure, 69–73 comm, 37 measure_seq, 74	gpp, 89	invperm, 58
absm, 28 absq, 29 adjoint, 30 anticomm, 30 anticomm, 30 apply, 31–33 applyCTRL, 33, 34 applyFFQ, 35 applyTFQ, 35 bigint, 26 bloch2rho, 36 bra, 26 choi2super, 37 chop, 116 cmat, 26 comm, 37 isprime, 60 ket, 28 kraus2choi, 60 kraus2super, 61 kron, 61, 62 kronpow, 63 lom, 63, 64 load, 64 load, 64 loadMATLAB, 65, 66 logme, 67 logmegativity, 67 marginalX, 68 maxn, 116 maxn, 116 measure, 69–73 comm, 37 isprime, 60 ket, 28 kraus2choi, 60 kraus2choi, 60 kraus2choi, 60 logmegativity, 63 marginalX, 68 maxn, 116 measure, 69–73 measure_seq, 74		ip, 59
adjoint, 30 anticomm, 30 anticomm, 30 apply, 31–33 applyCTRL, 33, 34 applyFFQ, 35 avg, 36 bigint, 26 bloch2rho, 36 bloch2rho, 36 choi2super, 37 chop, 116 cmat, 26 comm, 37 kraus2choi, 60 kraus2super, 61 kron, 61, 62 kronpow, 63 lom, 63, 64 load, 64 load, 64 loadMATLAB, 65, 66 logdet, 66 logdet, 66 logm, 67 marginalX, 68 marginalX, 68 maxn, 116 measure, 69–73 measure_seq, 74		isprime, 60
adjoint, 30 anticomm, 30 anticomm, 30 apply, 31–33 applyCTRL, 33, 34 applyFFQ, 35 applyTFQ, 35 avg, 36 bigint, 26 bloch2rho, 36 bloch2rho, 36 choi2super, 37 chop, 116 cmat, 26 comm, 37 kraus2super, 61 kron, 61, 62 kronpow, 63 lcm, 63, 64 load, 64 load, 64 load, 64 logdet, 66 logdet, 66 logm, 67 lognegativity, 67 marginalX, 68 marginalY, 68 maxn, 116 measure, 69–73 comm, 37	•	ket, 28
anticomm, 30	•	kraus2choi, 60
apply, 31–33 kron, 61, 62 kronpow, 63 applyQFT, 35 lcm, 63, 64 applyTFQ, 35 load, 64 avg, 36 loadMATLAB, 65, 66 bigint, 26 logdet, 66 bloch2rho, 36 logm, 67 bra, 26 choi2kraus, 36 choi2super, 37 marginalX, 68 choi2super, 37 chop, 116 measure, 69–73 comm, 37 kron, 61, 62 kron, 62 kron, 63, 64 load, 64		kraus2super, 61
applyCTRL, 33, 34 applyQFT, 35 applyTFQ, 35 avg, 36 bigint, 26 bloch2rho, 36 bra, 26 choi2kraus, 36 choi2super, 37 chop, 116 cmat, 26 comm, 37 kronpow, 63 lcm, 63, 64 load, 64 load, 64 loadMATLAB, 65, 66 logdet, 66 logme, 67 lognegativity, 67 marginalX, 68 marginalY, 68 maxn, 116 measure, 69–73 measure_seq, 74		kron, 61, 62
applyQFT, 35 applyTFQ, 35 avg, 36 bigint, 26 bloch2rho, 36 bra, 26 choi2kraus, 36 choi2super, 37 chop, 116 cmat, 26 comm, 37 lom, 63, 64 load, 64 load, 64 loadMATLAB, 65, 66 logdet, 66 logmegativity, 67 marginalX, 68 marginalX, 68 maxn, 116 measure, 69–73 measure_seq, 74	• • •	kronpow, 63
applyTFQ, 35 avg, 36 bigint, 26 bloch2rho, 36 bra, 26 choi2kraus, 36 choi2super, 37 chop, 116 cmat, 26 comm, 37 load, 64 loadMATLAB, 65, 66 logdet, 66 logm, 67 lognegativity, 67 marginalX, 68 marginalY, 68 maxn, 116 measure, 69–73 measure_seq, 74	• • •	lcm, 63, 64
avg, 36 loadMATLAB, 65, 66 bigint, 26 logdet, 66 logm, 67 logm, 67 bra, 26 lognegativity, 67 choi2kraus, 36 marginalX, 68 choi2super, 37 marginalY, 68 chop, 116 maxn, 116 cmat, 26 measure, 69–73 comm, 37 measure_seq, 74	• • •	load, 64
bigint, 26 bloch2rho, 36 bra, 26 choi2kraus, 36 chop, 116 cmat, 26 comm, 37 bigint, 26 blogdet, 66 logm, 67 lognegativity, 67 marginalX, 68 marginalY, 68 maxn, 116 measure, 69–73 measure_seq, 74	• • •	
bloch2rho, 36 bra, 26 bra, 26 choi2kraus, 36 choi2super, 37 choi, 116 cmat, 26 cmat, 26 comm, 37 logm, 67 lognegativity, 67 marginalX, 68 marginalY, 68 maxn, 116 measure, 69–73 measure_seq, 74		
bra, 26 lognegativity, 67 choi2kraus, 36 marginalX, 68 choi2super, 37 marginalY, 68 chop, 116 maxn, 116 cmat, 26 measure, 69–73 comm, 37 measure_seq, 74		_
choi2kraus, 36 marginalX, 68 choi2super, 37 marginalY, 68 chop, 116 maxn, 116 cmat, 26 measure, 69–73 comm, 37 measure_seq, 74		
choi2super, 37 marginalY, 68 chop, 116 maxn, 116 cmat, 26 measure, 69–73 comm, 37 measure_seq, 74		
chop, 116 maxn, 116 cmat, 26 measure, 69–73 comm, 37 measure_seq, 74		-
cmat, 26 measure, 69–73 comm, 37 measure_seq, 74	·	•
comm, 37 measure_seq, 74	•	
_ •		
complement, co		_ •

modinv, 76	transpose, 113
modmul, 77	tsallis, 113, 114
modpow, 77	uniform, 114
mprj, 78	var, 115
multiidx2n, 79	x2contfrac, 115
n2multiidx, 79	qpp.h, 385
negativity, 80	QPP_UNUSED_, 386
norm, 81	qpp::Bit_circuit, 129
normalize, 81	Bit_circuit, 131
omega, 81	CNOT, 131
operator"" _i, 82	Dynamic_bitset, 132
pi, 116	FRED, 132
powm, 82	gate_count, 134
prj, 82	NOT, 132
prod, 83, 84	reset, 132
ptrace, 84, 85	SWAP, 133
ptrace1, 85, 86	TOF, 133
ptrace2, 86, 87	X, 133
ptranspose, 87, 88	qpp::Bit_circuit::Gate_count, 170
QFT, 88	CNOT, 170
qmutualinfo, 89	FRED, 171
rand, 90–92	NOT, 171
randH, 92	SWAP, 171
randidx, 93	TOF, 171
randket, 93	X, 171
randkraus, 93	qpp::Codes, 134
randn, 94, 95	∼Codes, 136
randperm, 96	Codes, 136
randprime, 96	codeword, 136
randprob, 97	internal::Singleton< const Codes >, 137
randrho, 97	Type, 135
randU, 97	gpp::Dynamic bitset, 155
randV, 98	~Dynamic_bitset, 158
renyi, 98, 99	all, 158
reshape, 99	any, 158
rho2bloch, 100	count, 158
rho2pure, 100	data, 158
save, 101	display, 159
saveMATLAB, 101, 102	Dynamic_bitset, 157
schatten, 102	flip, 159
schmidtA, 103	get, 160
schmidtB, 103, 104	index_, 160
schmidtcoeffs, 104, 105	N_, 165
schmidtprobs, 105, 106	none, 160
sigma, 106	offset_, 161
sinm, 107	operator!=, 161
spectralpowm, 107	operator-, 161
sqrtm, 108	operator==, 162
sum, 108, 109	rand, 162, 163
super2choi, 109	reset, 163
svals, 110	set, 163, 164
svais, 110 svd, 110	size, 164
svd, 110 svdU, 110	storage_size, 164
svdV, 111	
	storage_size_, 165
syspermute, 111, 112 TFQ, 112	storage_type, 157
	to_string, 164
to_void, 28	v_, 165
trace, 112	value_type, 157

qpp::Gates, 172	Ks_, 246
\sim Gates, 174	noise_type, 241
CNOTba, 183	NoiseBase, 241
CNOT, 183	operator(), 244, 245
CTRL, 175	probs_, 246
CZ, 183	qpp::NoiseBase< T >, 239
expandout, 175, 176	qpp::NoiseType, 246
FRED, 183	qpp::NoiseType::StateDependent, 325
Fd, 177	qpp::NoiseType::StateIndependent, 325
Gates, 174	qpp::QCircuit, 267
get_name, 178	~QCircuit, 273
H, 183	begin, 273, 274
ld, 178	cCTRL_custom, 276
ld2, 184	cCTRL, 274–276
•	
internal::Singleton< const Gates >, 183	CTRL_custom, 279
MODMUL, 178	CTRL, 277, 278
Rn, 179	cbegin, 274
RX, 179	cend, 276
RY, 180	const_iterator, 271
RZ, 180	count_, 292
S, 184	d_, 292
SWAPd, 180	depth_, 292
SWAP, 184	display, 279
T, 184	end, 279, 280
TOF, 184	gate, 280, 281
X, 184	gate_custom, 281
Xd, 182	gate_fan, 282, 283
Y, 185	GateType, 271
Z, 185	gates_, 292
Zd, 182	get_d, <mark>283</mark>
qpp::IDisplay, 189	get_gate_count, 283
~IDisplay, 190	get_gate_depth, 284
display, 191	get_gates_, 284
IDisplay, 190	get_measured, 284, 285
operator<<, 191	get measurement count, 285
operator=, 191	get_measurements_, 286
qpp::IJSON, 192	
	get_name, 286
~IJSON, 193	get_nc, 286
IJSON, 192, 193	get_non_measured, 286
operator=, 193	get_nq, 287
to_JSON, 193	get_step_count, 287
qpp::lnit, 194	MeasureType, 272
∼Init, 195	measured_, 292
Init, 195	measurement_count_, 292
internal::Singleton< const Init >, 195	measurements_, 293
qpp::NoiseBase	measureV, 287, 288
\sim NoiseBase, 242	measureZ, 288
compute_probs_, 242	name_, 293
compute_state_, 242	nc_, 293
d_, 245	nq_, 293
generated_, 245	operator<<, 290, 291
get_Ks, 243	QCircuit, 273
get_d, 243	QEngine, 291
get_last_idx, 243	QFT, 288
get_last_K, 244	step_types_, 293
get_last_p, 244	StepType, 272
get_probs, 244	TFQ, 289
i_, 245	to_JSON, 289
, 2 10	10_00011, 200

cirt_187 gate_197 gate_type_187 GateStep, 186 name_187 target_187 qpc_CCircuit.MeasureStep, 235 c_reg_238 mats_236 measurement_type_238 mats_236 measurement_type_236 name_ye_137 terror_ye_237 target_1237 qpc_CCircuit.iterator, 212 difference_type, 213 elem_217 iterator_category_c13 operator-s_215 operator-s_215 operator-s_215 operator-s_216 pointer_213 qc_217 reference_214 set_end216 set_end350 measurements_pp351 operator-s_350 gates ip350 ip350 measurements_pl351 operator-a_360 gates ip350 popage_11,331 set_end288 popage_11,331 popage_298 get_init_298 get_init_298 get_init_298 get_init_298 get_pis_300 get_pis_300 ports_302 pis_302 ports_303		
gale187 galelype187 GateStep186 name187 qateStep186 name187 qateStep186 name187 qpp::Cultrit.MeasureStep235 cr_eg236 mass236 mass236 MeasureStep236 measurement_lype236 name237 qpp::Cultrit.lenamin_lype326 name237 qpp::Cultrit.lenamin_lype326 name_237 qpp::Cultrit.lenamin_lype336 name_237 qpp::Cultrit.lenamin_lype336 name_237 qpp::Cultrit.lenamin_lype336 name_237 qpp::Cultrit.lenamin_lype336 name_237 qpp::Cultrit.lenamin_lype336 name_237 qpp::Cultrit.lenamin_lype338 qpp::Cultrit.lenamin_lype338 qultrit.lenamin_lype338 qultrit.lenamin_lype348 qultrit.lenamin_lype349 qultrit.lenamin_lype	qpp::QCircuit::GateStep, 185	reset, 301
Qate Step. 186	-	
CateStep, 186 to JSON, 302 name187 target_, 187 target_, 187 Qpp::QubitAmplitudeDampingNoise, 303 qpp::QubitBmplitudeDampingNoise, 304 qpp::QubitBmplitudeDampingNoise, 304 qpp::QubitBitFlipNoise, 305 QubitBitFlipNoise, 306 massurestep, 236 qpp::QubitBitFlhaseFlipNoise, 306 measurement_type_, 236 qpp::QubitBitPhaseFlipNoise, 306 name_, 237 qpp::QubitBitPhaseFlipNoise, 306 target_, 237 qpp::QubitBitPhaseFlipNoise, 306 qpp::QubitPhaseFlipNoise, 306 qpp::QubitPhaseFlipNoise, 306 qpp::QubitPhaseFlipNoise, 306 qpp::QubitPhaseFlipNoise, 306 qpp::QubitPhaseFlipNoise, 307 qpp::QubitPhaseFlipNoise, 309 qpp::QubitPhaseFlipNoise, 309 QubitPhasePlipNoise, 310 qpp::QubitPhaseFlipNoise, 311 qpp::QubitPhaseFlipNoise, 311 qpp::QubitPhaseFlipNoise, 311 qpp::QubitPhaseFlipNoise, 311 qpp::QubitPhaseFlipNoise, 311 qpp::QubitPhaseFlipNoise, 311 qpp::QubitPhaseFlipNoise, 311 qpp::QubitPhaseFlipNoise, 311 qpp::QubitPhaseFlipNoise, 314 qpp::QubitPhaseFlipNoise, 316 qpp::QubitPhaseFlipNoise, 316 qpp::QubitPhaseFlipNoise, 316 <td< td=""><td>· —</td><td></td></td<>	· —	
name 187 target 187 qpp::Oclicuit-MeasureStep, 235 c_reg 236 mast 236 mast 236 mast 236 measurement_type 236 name 237 qpp::Oclicuit-iterator, 212 difference_type, 213 elem 217 iterator, 214 iterator_ 244 operatore, 215 operatore, 215 operatore, 215 operatore, 216 pointer, 213 qc 217 reference, 214 set_begin 216 sot_end		
target187 qpp::Colircult::MeasureStep, 235	•	_
app::Ocircuit::MeasureStep, 235 app::Ocircuit::MeasureStep, 236 c_reg236 Qpp::Ocircuit::MeasureStep, 236 mats236 app::Ocircuit::MeaseFilpNoise, 306 measurement_type236 app::Ocircuit::MeaseFilpNoise, 307 measurement_type236 app::Ocircuit::MeaseRipNoise, 309 arget237 app::Ocircuit::Terator, 212 difference_type, 213 aclem217 elem217 QubitPhaseFilpNoise, 310 operator, 214 app::Ocircuit:depolarizingNoise, 311 operator, 214 app::Ocircuit:depolarizingNoise, 314 fill_Ks316 app::Ocircuit:depolarizingNoise, 315 operator=, 216 app::Ocircuit:depolarizingNoise, 316 operator=, 216 app::Ocircuit:depolarizingNoise, 316 operator=, 216 app::Ocircuit:depolarizingNoise, 316 <td></td> <td></td>		
C_reg236 mats236 mats236 MeasureStep, 236 measurement_type236 name237 target237 qpp::Oclircut::iterator, 212 difference_type_213 elem217 iterator, 214 iterator_category, 213 operator+_, 215 operator, 215 operator-=, 216 pointer, 213 qc217 reference, 214 set_begin216 set_end216 set_end216 set_end216 set_end350 gates_ip350 ip350 measurements_ip351 operator-=, 350 type351 qpp::Oclircut::iterator:value_type348 display, 297 que_type_gc351 qpp::Oclircutiticrator.value_type_gpe_pct_end_masured_t299 get_measured_t299 get_ref_ix, 300 perator-=, 302 pi302 Qet_eleitve_pos300 poprator-=, 302 probs302 pi302 Qet_ref_ative_pos302 QubitiPepolarizingNoise, 309 QubitiPhaseDampingNoise, 309 QubitiPhasePlapNoise, 309 QubitiPhasePlapNoise, 311 qpp::Oclircuti::iterator.value_type_gcdisplay, 297 display_250 part251 qpp::Oclircutiticrator.value_type348 display_297 display_297 display_297 qisp302 qet_ref_ative_pos300 qet_ref_ative_pos300 qet_ref_ative_pos300 qet_ref_ative_pos300 qet_ref_ative_pos300 qet_ref_ative_pos300 qet_ref_ative_pos300 QubitiPhasePlapNoise, 309 QubitiPhasePlapNoise, 319 qpp::OutlitiPhasePlapNoise, 310 qpp::OutlitiPhasePlapNoise, 311 qpp::OutlitiPhasePlapNoise, 312 qpp::OutlitiPhasePlapNoise, 312 qpp::OutlitiPhasePlapNoise, 312 qpp::OutlitiPhasePlapNoise, 310 qpp::OutlitiPhasePlapNoise, 310 qpp::OutlitiPhasePlapNoise, 311 qpp::OutlitiPhasePlapNoise, 316 qpp::OutlitiPhasePlapNoise, 316 qpp::OutlitiPhasePlapNoise, 316 qpp::OutlitiPhasePlapNoise, 316 qpp::OutlitiPhaseP	· —	• • •
mats_236 MeasureStep, 236 measurement_type_, 236 measurement_type_, 236 measurement_type_, 236 name_, 237 disper_237 disper_237 difference_type_, 213 elem217 iterator, 214 difference_type_, 213 operatorl=, 214 operatorl=, 215 operatorl=, 215 operatorl=, 215 operatorl=, 216 pointer, 213 qc217 reference_ 214 set_begin_, 216 set_end216 value_type_, 214 display, 350 gates_ip_, 350 measurements_ip_, 351 operatorl=, 350 measurements_ip_, 351 operatorl=, 399 value_type_, 349 value_type_, 294 value_type_, 294 value_type_, 294 value_type_, 297 display, 297 display, 297 display, 297 display, 297 display, 297 display, 298 get_oricuit, 298 get_measured, 299 get_pois_, 300 peratore_, 300 peratore_, 300 peratore_, 300 peratore_, 300 per_pointer_, 3		
MeasureStep, 236 measurement_type_, 236 name_, 237 target_, 237 target_, 237 qpp:CubitDepolarizingNoise, 308 QubitDepolarizingNoise, 309 qpp:QubitDepolarizingNoise, 309 qpp:QubitPhaseDampingNoise, 309 qpp:QubitPhaseDampingNoise, 310 qpp:QubitPhasePilpNoise, 311 QubitPhasePilpNoise, 311 QubitPhasePilpNoise, 311 QubitPhasePilpNoise, 311 QubitPhasePilpNoise, 311 QubitPhasePilpNoise, 311 QubitPhasePilpNoise, 314 fill_Ks_, 316 fill_probs_, 316 QuditDepolarizingNoise, 319 qpp:QubitPhasePilpNoise, 311 QubitPhasePilpNoise, 311 QubitPhasePilpNoise, 311 QubitPhasePilpNoise, 311 QubitPhasePilpNoise, 311 fill_Ks_, 316 fill_probs_, 316 QuditDepolarizingNoise, 310 qpp:QubitPhasePilpNoise, 310 qpp:QubitPhasePilpNoise, 310 qpp:QubitPhasePilpNoise, 311 QubitPhasePilpNoise, 311 QubitPhasePilpNoise, 311 QubitPhasePilpNoise, 311 QubitPhasePilpNoise, 311 QubitPhasePilpNoise, 311 qpp:QubitPhasePilpNoise, 316 Qpp:QubitPhasePilpNoise, 314 fill_Ks_, 316 fill_probs_, 316 QuditDepolarizingNoise, 316 qpp:QubitPhasePilpNoise, 311 qpp:QubitPhasePilpNoise, 311 qpp:QubitPhasePilpNoise, 311 qpp:QubitPhasePilpNoise, 311 qpp:QubitPhasePilpNoise, 311 qpp:QubitPhasePilpNoise, 311 qpp:QubitPhasePilpNoise, 312 qpp:QubitPhasePilpNoise, 312 qpp:QubitPhasePilpNoise, 314 fill_Ks_, 316 fill_Ks_, 316 fill_probe_, 316 QuditPhasePilpNoise, 312 qpp:QubitPhasePilpNoise, 316 qpp:QubitPhasePilpNoise, 314 fill_Ks_, 316 fill_probe_, 316 qpp:QubitPhasePilpNoise, 316 qpp:QubitPhasePilpNoise		•
measurement_type236	mats_, 236	
name237 target237 qpp::Qclircult::lerator, 212 difference_type, 213 elem217 literator, 214 literator_category, 213 operatort=_215 operator=_215 operator=_215 operator=_216 pointer, 213 elem217 reference, 214 set_begin216 set_end216 value_type, 214 qpp::Qclircult::lerator::walue_type348 display, 350 gates_ip350 ip350 ip350 ip350 ip350 ip351 value_type349 value_type349 value_type349 value_type349 value_type0a351 qpp::Qclircingine, 294 ~CEngine, 297 disp302 execute, 297, 298 get_circuit, 298 get_not_measured, 299 get_probs302 pri302 pri302 pri302 pri302 pri302 pri300 prisaso prior_saso pri	MeasureStep, 236	
target_237 qpp::QubitPhaseDampingNoise, 309 qubitPhaseFlipNoise, 311 elem_217 iterator, 214 iterator category, 213 operator=, 215 operator=, 215 operator=, 215 operator=, 216 pointer, 213 qc217 reference, 214 set_begin_216 set_end_216 value_type_214 qpp::QubitPhaseFlipNoise, 311 fill_probs 316 OuditPhaseFlipNoise, 314 fill_probs 316 OuditDepolarizingNoise, 315 qpp::QubitPhaseFlipNoise, 315 qpp::QubitPhaseFlipNoise, 314 fill_probs 316 OuditDepolarizingNoise, 315 qpp::RandomDevices, 317 ~RandomDevices, 317 ~RandomDevices, 318 get_prng, 319 internat::Singleton< RandomDevices >, 320 load, 319 rpng 320 RandomDevices, 318 get_prng, 319 internat::Singleton< RandomDevices >, 320 load, 319 rpng 320 RandomDevices, 318 rd 320 save, 319 qpp::States, 328 boo, 330 bo1, 331 bot, 331 ppp::Qaricutt::Iterator::value_type 348 display, 350 bol, 331 bol, 331 ppp::Qaricutt::Iterator::Singleton const States >, 330 in 350 type 351 value_type 349 value_type 351 value_type 361 GHZ, 331 internat::Singleton const States >, 330 in 328 mes, 328 getmasured, 297 getcircutt, 298 getcircutt, 298 getcircutt, 298 getcircutt, 298 getoth, 298 getoth, 298 getoth, 299 getnotmeasured, 299 getpobs 300 ppt, 332 ppt, 332 ppt, 333 ppt, 333 ppt, 333 ppt, 332 ppt, 333 ppt, 334 ppt, 335 ppt, 335 ppt, 336 ppt, 344 ppt,	measurement_type_, 236	qpp::QubitDepolarizingNoise, 308
qpp::OCircuit::iterator, 212 GubitPhasePilipNoise, 310 difference_type, 213 qpp::QubitPhaseFilipNoise, 311 elem217 QubitPhaseFilipNoise, 312 iterator, 214 qpp::QuditDepolarizingNoise, 314 iterator_category, 213 fill_Ks316 operator+, 215 QuditDepolarizingNoise, 315 operator+, 215 QuditDepolarizingNoise, 315 operator-, 216 qpp::RandomDevices, 318 operator-, 216 get_pring, 319 pointer, 213 internal::Singletor<	name_, 237	QubitDepolarizingNoise, 309
difference_type, 213 elem217 elem217 iterator_214 iterator_category, 213 operatorl=, 214 operators-, 215 operators-, 215 operators-, 215 operators-, 216 opinter, 213 qc 217 reference, 214 set_begin 216 set_end 216 value_type, 214 dpp::OCircuit::iterator::value_type 348 display, 350 gates_ip 350 measurements_ip 351 operators-, 350 type 351 value_type 349 value_type_ 351 dpp::OEngine, 294	target_, 237	qpp::QubitPhaseDampingNoise, 309
elem217 iterator, 214 iterator, 214 iterator, 215 operator=, 215 operator=, 215 operator=, 216 operator=, 350 operator=, 301 operator=, 302 operator=, 302 operator=, 302 operator=, 302 operator=, 302 operator=, 296 operator=, 301 operator=, 206 operator=, 206 operator=, 207 operator=, 301 operator=, 206 operator=, 20	qpp::QCircuit::iterator, 212	QubitPhaseDampingNoise, 310
iterator, 214 iterator, 214 iterator_category, 213 operator=, 214 operator=, 215 operator++, 215 operator-+, 215 operator-+, 215 operator-=, 216 pointer, 213 qc 217 reference, 214 set_begin 216 set_end 216 set_end 216 square_space display, 350 gates_ip 350 ip 350 measurements_ip 351 operator=, 350 type 351 value_type_ qc 351 qpp::Carciniting, 294 ~QEngine, 297 display, 297 display, 298 get_dit, 298 get_measured, 299 get_probs 300 ppi 302 pet_ref_psi 300 ppi 302 pet_ref_psi 302 pet_gin 202 QEngine, 296 W, 333 lill_lill_Ks 316 lill_Ks 316 QuditDepolarizingNoise, 314 lill_Lycs 317 call_lill_Lycs 318 call_lill_Lycs 319 linternal::Singleton <randomdevices, 317="" 319="" call_day,="" linternal::singleton<randomdevices="">, 320 load, 319 promp 320 promp_</randomdevices,>	difference_type, 213	qpp::QubitPhaseFlipNoise, 311
iterator_category, 213 operatorl=, 214 operatorl=, 215 operator+, 215 operator+, 215 operator-, 215 operator-, 216 operator-, 216 operator-, 217 operator-, 218 operator-, 219 operator-, 210 operator-, 211 operator-, 211 operator-, 212 operator-, 213 operator-, 214 operator-, 215 operator-, 216 operator-, 216 set_begin_, 216 set_end_, 225 set_end_, 225 set_end_, 225 set_end_, 225 set_end_, 225 set_end_, 226 set_end_, 227 dis_, 326 set_end_, 227 dis_, 327 dis_, 327 dis_, 328 set_end_, 229 set_end	elem_, 217	QubitPhaseFlipNoise, 312
operator!=, 214 fill_probs 316 QuditDepolarizingNoise, 315 Operator*, 215 Operator*, 215 Operator=, 216 Operator=, 216 Operator=, 216 Operator=, 216 Operator=, 217 Operator=, 218 Operator=, 219 Operator=, 219 Operator=, 219 Operator=, 219 Operator=, 210 Operator=, 210 Operator=, 210 Operator=, 210 Operator=, 210 Operator=, 210 Operator=, 216 Operator=, 218 Operato	iterator, 214	qpp::QuditDepolarizingNoise, 314
operator*, 215 operator+, 215 operator-+, 215 operator, 216 operator, 216 operator, 216 operator, 216 operator, 216 operator, 216 operator, 213 operator, 213 operator, 214 pointer, 213 operator, 216 pointer, 213 operator, 216 pointer, 213 operator, 216 pointer, 213 operator, 216 pointer, 214 set_begin_, 216 set_end_, 216 set_end_, 216 set_end_, 216 set_end_, 216 set_end_, 215 ovalue_type, 214 dpp:::Circuit::tlerator::value_type_, 348 display, 350 gates_ip, 350 jp, 360 jp, 360 jp, 370 jp, 380 jp	iterator_category, 213	fill_Ks_, 316
operator++, 215 operator=, 216 operator=, 216 operator=, 217 operator=, 218 pointer, 213 qe217 reference, 214 set_begin_, 216 set_end_, 216 value_type, 214 qpp::Circuit::iterator::value_type_, 348 display, 350 qates_ip_, 350 ip_, 350 measurements_ip_, 351 operator=, 350 type351 value_type_ac_, 351 value_type_ac_, 351 value_type_ac_, 351 qpp::CEngine, 294 ~CEngine, 297 dits_, 302 execute, 297, 298 get_dit, 298 get_measured, 299 get_mot_measured, 299 get_pros, 300 pet_ref_psi, 300 get_ref_psi, 300 pet_rot_s, 302 pet, 302 Qengine, 296 despine, 296 despine, 297 despine, 299 get_psi, 300 get_ref_psi, 300 pet_ac_, 302 petates, 328 qpp::Calledine, 296 pool, 331 pool, 332 pet_ref_psi, 300 pet_ref_psi, 300 pet_ref_psi, 302 pet_not_measured, 299 pet_psi, 300 pet_ref_psi, 300 pet_ref_psi, 300 pet_ref_psi, 300 pet_ref_psi, 302 pet_not_measured, 299 pet_not_s, 302 psi, 302 Qengine, 296 W, 333	operator!=, 214	fill_probs_, 316
operator=, 215 operator==, 216 pointer, 213 q 217 reference, 214 set_begin 216 value_type, 214 qpp::\(\mathcal{Q}\) (Circuit:\(\pi\) (terrator) (te	operator*, 215	QuditDepolarizingNoise, 315
operator==, 216 pointer, 213 qc_, 217 reference, 214 set_begin_, 216 set_end_, 216 set_end_, 216 set_end_, 216 set_end_, 214 app::Clircuit:iterator::value_type_, 348 display, 350 gates_ip_, 350 ip_, 350 ip_, 350 measurements_ip_, 351 operator=, 350 type_, 351 value_type_, 349 value_type_, 349 value_type_, 349 value_type_, 349 value_type_, 351 value_type_, 351 value_type_, 351 value_type_, 359 display, 297 display, 297 display, 297 display, 297 display, 297 display, 298 get_circuit, 298 get_dits, 298 get_measured, 299 get_pring, 319 internal::Singleton < const States >, 330 internal::Singleton < const States >, 328 internal::Singleton < const States >,	operator++, 215	qpp::RandomDevices, 317
pointer, 213 qc_, 217 qc_, 217 reference, 214 set_begin_, 216 set_end_, 216 value_type, 214 qpp::\(\text{Ocircuit:iterator::value_type}\), 348 display, 350 measurements_ip_, 351 value_type_, 349 value_type_, 349 value_type_, 349 value_type_qc_, 351 value_type_qc_, 351 qpp::\(\text{Ocircuit:iterator::value_type}\) qpp:\(\text{Ocircuit:iterator::value_type}\), 350 measurements_ip_, 351 display, 350 measurements_ip_, 351 value_type_, 349 value_type_, 349 value_type_qc_, 351 qpp::\(\text{Ocircuit:iterator::value_type}\) qc_, 351 value_type_qc_, 351 qpp::\(\text{Ocircuit:iterator::value_type}\) qc_, 351 qpp::\(\text{Ocircuit:iterator::value_type}\) qc_, 351 value_type_qc_, 351 qpp::\(\text{Ocircuit:}\) qpe_t_dit_, 298 qpt_dit_, 298 qpt_dit_, 298 qpt_measured, 299 qpt_polon, 332 qpt_measured, 299 qpt_polon, 332 qpt_polon, 300 qpt_polon, 333 qpt_ref_polon, 300 qpt_ref_polon, 300 qpt_relative_pos_, 300 qpt_si_, 302 qpi_, 302 qpi_, 302 qpi_not_, 296 \text{V, 333} \text{V, 333}	operator=, 215	\sim RandomDevices, 318
qc_, 217 load, 319 reference, 214 prng_, 320 set_begin_, 216 RandomDevices, 318 set_end_, 216 rd_, 320 value_type, 214 save, 319 qpp::CCircuit::iterator::value_type_, 348 qpp::States, 325 display, 350 Sates, 328 gates_ip_, 350 b00, 330 ip_, 350 b01, 331 measurements_ip_, 351 b10, 331 type_, 351 GHZ, 331 value_type_qo_, 351 internal::Singleton < const States >, 330 value_type_qo_, 351 jn, 328 qpp::QEngine, 294 mes, 328 ~QEngine, 297 minus, 329 display, 297 one, 329 display, 297 one, 329 dit_, 302 pGHZ, 332 execute, 297, 298 pb00, 331 get_circuit, 298 pb11, 331 get_dit, 298 pb10, 332 get_measured, 299 pk, 332 get_psi, 300 px1, 332 get_psi, 300 py0, 333 get_ref_psi, 300 py0, 333 get_relative_pos_, 301 pz0, 333 probs_, 302 <	operator==, 216	get_prng, 319
reference, 214 set_begin 216 set_end_, 216 rel 320 rel	pointer, 213	internal::Singleton < RandomDevices >, 320
set_begin_, 216 set_end_, 216 value_type, 214 qpp::\text{QCircuit::iterator::value_type_, 348} qpp::\text{Qpp::\text{Qcircuit::iterator::value_type_, 348} qpp::\text{States, 328} qstes_ip_, 350 ip_, 350 measurements_ip_, 351 operator=, 350 type_, 351 value_type_, 349 value_type_qc_, 351 value_type_qc_, 351 qpp::\text{QEngine, 294} \times_QEngine, 297 display, 297 display, 297 dist_, 302 execute, 297, 298 get_circuit, 298 get_dit, 298 get_measured, 299 get_measured, 299 get_not_measured, 299 get_probs, 299 get_probs, 299 get_probs, 299 get_probs, 299 get_probs_, 300 get_ref_psi, 300 get_ref_psi, 300 poperator=, 301 probs_, 302 QEngine, 296 W, 333 Palsa RandomDevices, 318 rd_, 320 save, 319 qpp::\text{States, 328} \text{States, 328} \text{States, 328} \text{States, 328} \text{Value_type_call} save, 319 qpp::\text{States, 328} \text{States, 328} \text{States, 328} \text{Value_type_call} save, 319 qpp::\text{States, 328} \text{States, 328} \text{Value_type_call} save, 319 qpp::\text{States, 328} \text{States, 328} \text{Value_type_call} save, 319 qpp::\text{States, 328} \text{Value_type_call} save, 319 save, 328 save,	qc_, 217	load, 319
set_end_, 216 rd_, 320 value_type, 214 save, 319 qpp::QCircult::iterator::value_type_, 348 qpp::States, 325 display, 350 ~States, 328 gates_ip_, 350 b00, 330 ip_, 350 b01, 331 measurements_ip_, 351 b10, 331 operator=, 350 b11, 331 type_, 349 internal::Singleton< const States >, 330 value_type_qc_, 351 jn, 328 qpp::QEngine, 294 mes, 328 ~QEngine, 297 minus, 329 display, 297 one, 329 dits_, 302 pGHZ, 332 execute, 297, 298 pb00, 331 get_circuit, 298 pb01, 331 get_dit, 298 pb11, 332 get_measured, 299 pb10, 332 get_measured, 299 pW, 332 get_probs, 299 px0, 332 get_pet_psi, 300 px1, 332 get_ref_psi, 300 py0, 333 operator=, 301 pz0, 333 probs_, 302 ps1, 302 QEngine, 296 W, 333	reference, 214	prng_, 320
value_type, 214 save, 319 qpp::QCircuit::tierator::value_type_, 348 qpp::States, 325 display, 350 ~States, 328 gates_ip_, 350 b00, 330 ip 350 b01, 331 measurements_ip_, 351 b10, 331 operator=, 350 b11, 331 type_, 351 GHZ, 331 value_type_, 349 internal::Singleton < const States >, 330 value_type_qc_, 351 jn, 328 qpp::QEngine, 294 mes, 328 ~QEngine, 297 minus, 329 display, 297 one, 329 dist_, 302 pGHZ, 332 execute, 297, 298 pb00, 331 get_circuit, 298 pb01, 331 get_dit, 298 pb10, 332 get_measured, 299 pb11, 332 get_measured, 299 pw, 332 get_probs, 299 px0, 332 get_pet_probs, 299 px0, 332 get_ref_psi, 300 py1, 333 operator=, 301 pz0, 333 probs_, 302 p21, 333 QEngine, 296 W, 333	set_begin_, 216	RandomDevices, 318
qpp::QCirculit:iterator::value_type, 348 qpp::States, 325 display, 350 ~States, 328 gates_ip, 350 b00, 330 ip, 350 b01, 331 measurements_ip_, 351 b10, 331 operator=, 350 b11, 331 type, 351 GHZ, 331 value_type_, 349 internal::Singleton < const States >, 330 value_type_qc_, 351 jn, 328 qpp::QEngine, 297 mes, 328 ~QEngine, 297 minus, 329 display, 297 one, 329 dits_, 302 pGHZ, 332 execute, 297, 298 pb00, 331 get_circuit, 298 pb01, 331 get_dit, 298 pb110, 332 get_measured, 299 plus, 329 get_mosured, 299 pW, 332 get_probs, 299 px0, 332 get_ref_psi, 300 px1, 332 get_ref_psi, 300 py0, 333 get_relative_pos_, 300 py1, 333 operator=, 301 pz0, 333 probs_, 302 ps1, 332 QEngine, 296 W, 333	set_end_, 216	rd_, 320
display, 350 ~States, 328 gates_ip_, 350 b00, 330 ip_, 350 b01, 331 measurements_ip_, 351 b10, 331 operator=, 350 b11, 331 type_, 351 GHZ, 331 value_type_, 349 internal::Singleton < const States >, 330 value_type_qc_, 351 jn, 328 qpp::QEngine, 294 mes, 328 ~QEngine, 297 minus, 329 display, 297 one, 329 display, 297 one, 329 display, 297 one, 329 get_circuit, 298 pb00, 331 get_circuit, 298 pb00, 331 get_dit, 298 pb11, 332 get_measured, 299 plus, 329 get_measured, 299 pW, 332 get_probs, 299 pX0, 332 get_probs, 299 px0, 332 get_ref_psi, 300 px1, 332 get_relative_pos_, 300 py1, 333 operator=, 301 pz0, 333 probs_, 302 pz1, 333 psi_, 302 States, 328 QEngine, 296 W, 333	value_type, 214	save, 319
gates_ip_, 350 ip_, 350 bo0, 330 ip_, 350 measurements_ip_, 351 operator=, 350 type_, 351 type_, 351 value_type_, 349 value_type_qc_, 351 qpp::QEngine, 294	qpp::QCircuit::iterator::value_type_, 348	qpp::States, 325
ip 350 measurements_ip 351 operator=, 350 type 351 value_type_ 349 value_type_qc_, 351 qpp::QEngine, 294	display, 350	\sim States, 328
measurements_ip_, 351 operator=, 350 type_, 351 value_type_, 349 value_type_qc_, 351 value_type_qc_, 351 operator=, 350 internal::Singleton< const States >, 330 value_type_qc_, 351 internal::Singleton< const States >, 330 value_type_qc_, 351 internal::Singleton< const States >, 330 internal::Singleton< const States >, 330 internal::Singleton< const States >, 330 value_type_qc_, 351 internal::Singleton< const States >, 330 internal::Singleton< const States >, 328 internal::Singleton	gates_ip_, 350	b00, 330
operator=, 350 type_, 351 type_, 351 value_type_, 349 value_type_qc_, 351 querestype_qc_, 351 internal::Singleton < const States >, 330 jn, 328 querestype_qc_, 351 querestype_qc_, 351 jn, 328 querestype_qc_, 351 jn, 328 querestype_qc_, 351 mes, 328 mes, 328 peggget get, 329 peget, 332 pet, 332 querestype_qc_, 351 perestype_qc_, 331 perestype_qc_, 351 perestype_qc_, 332 pet, 298 pet, 332 querestype_qc_, 300 pet, 332 querestype_qc_, 300 pet, 332 querestype_qc_, 300 pet, 332 querestype_qc_, 301 perestype_qc_, 302 pet, 302 pet, 302 Querestype_qc_, 328 Querestype_qc_, 331 probs_, 302 pet, 302 Querestype_qc_, 331 probs_, 302 pet, 333 querestype_qc_, 331 probs_, 302 pet, 333 pet, 334 pet, 334 pet, 335 pet, 336 pet, 336 pet, 336 pet, 336 pet, 337	ip_, 350	•
type 351 value_type 349 value_type_qc 351 qpp::QEngine, 294	measurements_ip_, 351	b10, 331
value_type_, 349 internal::Singleton < const States >, 330 value_type_qc_, 351 jn, 328 qpp::QEngine, 294 mes, 328 ~QEngine, 297 minus, 329 display, 297 one, 329 dits_, 302 pGHZ, 332 execute, 297, 298 pb00, 331 get_circuit, 298 pb01, 331 get_dit, 298 pb10, 332 get_dits, 298 pb11, 332 get_measured, 299 plus, 329 get_not_measured, 299 pW, 332 get_probs, 299 px0, 332 get_psi, 300 px1, 332 get_ref_psi, 300 py0, 333 get_relative_pos_, 300 py1, 333 operator=, 301 pz0, 333 probs_, 302 pz1, 333 psi_, 302 States, 328 QEngine, 296 W, 333	operator=, 350	b11, 331
value_type_qc_, 351 qpp::QEngine, 294		GHZ, 331
qpp::QEngine, 297 mes, 328 ~QEngine, 297 minus, 329 display, 297 one, 329 dits_, 302 pGHZ, 332 execute, 297, 298 pb00, 331 get_circuit, 298 pb01, 331 get_dit, 298 pb10, 332 get_measured, 299 plus, 329 get_not_measured, 299 pW, 332 get_probs, 299 px0, 332 get_psi, 300 px1, 332 get_ref_psi, 300 py0, 333 get_relative_pos_, 300 py1, 333 operator=, 301 pz0, 333 probs_, 302 pz1, 333 psi_, 302 States, 328 QEngine, 296 W, 333	value_type_, 349	_
~QEngine, 297 minus, 329 display, 297 one, 329 dits_, 302 pGHZ, 332 execute, 297, 298 pb00, 331 get_circuit, 298 pb10, 332 get_dit, 298 pb10, 332 get_measured, 299 plus, 329 get_not_measured, 299 pW, 332 get_probs, 299 px0, 332 get_psi, 300 px1, 332 get_ref_psi, 300 py0, 333 get_relative_pos_, 300 py1, 333 operator=, 301 pz0, 333 probs_, 302 pz1, 333 psi_, 302 States, 328 QEngine, 296 W, 333	value_type_qc_, 351	jn, 328
display, 297 one, 329 dits_, 302 pGHZ, 332 execute, 297, 298 pb00, 331 get_circuit, 298 pb01, 331 get_dit, 298 pb10, 332 get_measured, 299 plus, 329 get_not_measured, 299 pW, 332 get_probs, 299 px0, 332 get_psi, 300 px1, 332 get_ref_psi, 300 py0, 333 get_relative_pos_, 300 py1, 333 operator=, 301 pz0, 333 probs_, 302 pz1, 333 psi_, 302 States, 328 QEngine, 296 W, 333	qpp::QEngine, 294	mes, 328
dits_, 302 execute, 297, 298 pb00, 331 get_circuit, 298 pb10, 331 get_dit, 298 pb10, 332 get_dits, 298 pb11, 332 get_measured, 299 get_not_measured, 299 get_probs, 299 get_probs, 299 get_psi, 300 px1, 332 get_ref_psi, 300 get_ref_psi, 300 py0, 333 get_relative_pos_, 300 pp1, 333 operator=, 301 pz0, 333 probs_, 302 psi_, 302 QEngine, 296 pb00, 331 pb01, 332 pb11, 332 pb11, 332 pv1, 332 pv3, 333 p	-	minus, 329
execute, 297, 298 get_circuit, 298 get_dit, 298 get_dits, 298 get_measured, 299 get_not_measured, 299 get_probs, 299 get_psi, 300 get_ref_psi, 300 get_relative_pos_, 300 operator=, 301 probs_, 302 QEngine, 296 pb00, 331 pb01, 331 pb01, 332 pb11, 332 pb11, 332 pb11, 332 pb11, 332 pb2, 333 pp33 pp4_relative_pos_, 300 py1, 333 pz1, 333 pz1, 333 pz1, 333 pz1, 333 pz1, 333 px1, 333		
get_circuit, 298 pb01, 331 get_dit, 298 pb10, 332 get_dits, 298 pb11, 332 get_measured, 299 plus, 329 get_probs, 299 pW, 332 get_probs, 299 px0, 332 get_psi, 300 px1, 332 get_ref_psi, 300 py0, 333 get_relative_pos_, 300 py1, 333 operator=, 301 pz0, 333 probs_, 302 pz1, 333 psi_, 302 States, 328 QEngine, 296 W, 333		·
get_dit, 298		•
get_dits, 298 get_measured, 299 get_not_measured, 299 get_probs, 299 get_probs, 300 get_ref_psi, 300 get_relative_pos_, 300 ppt, 333 get_relative_pos_, 300 ppt, 333 probs_, 302 ppt, 302 QEngine, 296 ppt, 332 ppt, 333 ppt, 332 ppt, 333 ppt, 334 ppt, 334 ppt, 335 p	- -	•
get_measured, 299 get_not_measured, 299 get_probs, 299 get_probs, 299 get_psi, 300 get_ref_psi, 300 get_ref_psi, 300 get_relative_pos_, 300 operator=, 301 probs_, 302 psi_, 302 QEngine, 296 plus, 329 pW, 332 pv, 332 px1, 332 px1, 333 prob, 332 pz1, 333 pz1, 333 pz1, 333 px1, 333 px2, 302 QEngine, 296 plus, 329 pw, 332 px1, 332 px1, 332 px2, 333 px3,	· —	·
get_not_measured, 299 get_probs, 299 get_psi, 300 get_ref_psi, 300 get_relative_pos_, 300 operator=, 301 probs_, 302 psi_, 302 QEngine, 296 pW, 332 px0, 332 px1, 332 px0, 333 py1, 333 pz0, 333 pz1, 333 pz1, 333 pz1, 333 px1, 333 px2, 302 QEngine, 296 pW, 332 pw3, 332 pw3, 332 pw3, 332 pw3, 333 pw3	- -	•
get_probs, 299	- -	•
get_psi, 300 px1, 332 get_ref_psi, 300 py0, 333 get_relative_pos_, 300 py1, 333 operator=, 301 pz0, 333 probs_, 302 pz1, 333 psi_, 302 States, 328 QEngine, 296 W, 333		·
get_ref_psi, 300 py0, 333 get_relative_pos_, 300 py1, 333 operator=, 301 pz0, 333 probs_, 302 pz1, 333 psi_, 302 States, 328 QEngine, 296 W, 333		•
get_relative_pos_, 300 py1, 333 operator=, 301 pz0, 333 probs_, 302 pz1, 333 psi_, 302 States, 328 QEngine, 296 W, 333		•
operator=, 301 pz0, 333 probs_, 302 pz1, 333 psi_, 302 States, 328 QEngine, 296 W, 333		
probs_, 302 pz1, 333 psi_, 302 States, 328 QEngine, 296 W, 333		
psi_, 302 States, 328 QEngine, 296 W, 333	·	•
QEngine, 296 W, 333		•
-	• —	
qυ_, ουο xυ, 333		
	μ ν_, 3 03	λυ, σσσ

x1, 334	type_description, 222
y0, 334	qpp::exception::MatrixNotRvector, 223
y1, 334	Exception, 224
z0, 334	type_description, 224
z1, 334	qpp::exception::MatrixNotSquare, 225
zero, 330	Exception, 226
qpp::Timer	type_description, 226
∼Timer, 339	qpp::exception::MatrixNotSquareNorCvector, 227
display, 339	Exception, 228
end_, 341	type_description, 228
get_duration, 340	qpp::exception::MatrixNotSquareNorRvector, 229
operator=, 340	Exception, 230
start_, 341	type_description, 230
tic, 340	qpp::exception::MatrixNotSquareNorVector, 231
tics, 341	Exception, 232
Timer, 338, 339	type_description, 232
toc, 341	qpp::exception::MatrixNotVector, 233
qpp::Timer< T, CLOCK_T >, 337	Exception, 234
qpp::exception, 116	type_description, 234
qpp::exception::CustomException, 137	qpp::exception::NoCodeword, 237
CustomException, 138	Exception, 238
type_description, 139	type_description, 239
what_, 139	qpp::exception::NotBipartite, 247
qpp::exception::DimsInvalid, 140	Exception, 248
Exception, 141	type_description, 248
type_description, 141	qpp::exception::NotImplemented, 249
qpp::exception::DimsMismatchCvector, 142	Exception, 250
Exception, 143	type_description, 250
type_description, 143	qpp::exception::NotQubitCvector, 251
qpp::exception::DimsMismatchMatrix, 144	Exception, 252
Exception, 145	type_description, 252
type_description, 145	qpp::exception::NotQubitMatrix, 253
qpp::exception::DimsMismatchRvector, 146	Exception, 254
Exception, 147	type_description, 254
type_description, 147	qpp::exception::NotQubitRvector, 255
qpp::exception::DimsMismatchVector, 148	Exception, 256
Exception, 149	type_description, 256
type_description, 149	qpp::exception::NotQubitSubsys, 257
qpp::exception::DimsNotEqual, 150	Exception, 258
Exception, 151	type_description, 258
type_description, 151	qpp::exception::NotQubitVector, 259
qpp::exception::Duplicates, 153	Exception, 260
Exception, 154	type_description, 260
type_description, 154	qpp::exception::OutOfRange, 261
qpp::exception::Exception, 166	Exception, 262
Exception, 169	type_description, 262
msg_, 170	qpp::exception::PermInvalid, 263
type_description, 169	Exception, 264
what, 169	type_description, 264
where_, 170	qpp::exception::PermMismatchDims, 265
qpp::exception::InvalidIterator, 196	Exception, 266
Exception, 197	type_description, 266
type_description, 197	qpp::exception::QuditAlreadyMeasured, 312
qpp::exception::MatrixMismatchSubsys, 219	Exception, 313
Exception, 220	type_description, 314
type_description, 220	qpp::exception::SizeMismatch, 323
qpp::exception::MatrixNotCvector, 221	Exception, 324
Exception, 222	type_description, 324

qpp::exception::SubsysMismatchDims, 335	p_, 203
Exception, 336	separator_, 203 start_, 203
type_description, 336	qpp::internal::IOManipPointer< PointerType >, 200
app::exception::TypeMismatch, 342	qpp::internal::IOManipRange
Exception, 343	display, 205
type_description, 344	end_, 206
app::exception::UndefinedType, 344	first , 206
Exception, 345 type_description, 346	IOManipRange, 205
qpp::exception::Unknown, 346	last_, 206
	operator=, 205
Exception, 347 type_description, 348	separator_, 206
qpp::exception::ZeroSize, 352	start_, 206
	qpp::internal::IOManipRange< InputIterator >, 204
Exception, 353	qpp::internal::KeyEqualEigen, 217
type_description, 353	operator(), 218
qpp::experimental, 118 qpp::internal, 118	qpp::internal::Singleton
	~Singleton, 322
check_cvector, 120	get_instance, 322
check_dims, 120 check_dims_match_cvect, 120	get_thread_local_instance, 322
	operator=, 322
check_dims_match_mat, 120	Singleton, 321, 322
check_dims_match_rvect, 120	qpp::internal::Singleton< T >, 320
check_eq_dims, 121	qpp::is_complex< std::complex< T >>, 208
check_matching_sizes, 121	qpp::is_complex< T >, 207
check_no_duplicates, 121	qpp::is_iterable< T, to_void< decltype(std::declval< T
check_nonzero_size, 121	>().begin()), decltype(std::declval< T >().↔
check_perm, 121	end()), decltype(*(std::declval< T >().←
check_qubit_cvector, 121	begin()))>>, 210
check_qubit_matrix, 122	qpp::is_iterable< T, typename >, 209
check_qubit_rvector, 122	qpp::is_matrix_expression< Derived >, 211
check_qubit_vector, 122	qpp::literals, 125
check_rvector, 122	operator"" _bra, 125
check_square_mat, 122	operator"" _i, 125
check_subsys_match_dims, 122	operator"" _ket, 126
check_vector, 123	operator"" _prj, 126
dirsum2, 123	qpp::make_void
get_dim_subsys, 123	type, 218
get_num_subsys, 123	qpp::make_void< Ts >, 218
hash_combine, 123	QubitAmplitudeDampingNoise
kron2, 123	qpp::QubitAmplitudeDampingNoise, 304
multiidx2n, 124	QubitBitFlipNoise
n2multiidx, 124	qpp::QubitBitFlipNoise, 306
variadic_vector_emplace, 124	QubitBitPhaseFlipNoise
qpp::internal::Display_Impl_, 152	qpp::QubitBitPhaseFlipNoise, 307
display_impl_, 152	QubitDepolarizingNoise
qpp::internal::HashEigen, 188	qpp::QubitDepolarizingNoise, 309
operator(), 188	QubitPhaseDampingNoise
qpp::internal::IOManipEigen, 198	qpp::QubitPhaseDampingNoise, 310
A_, 199	QubitPhaseFlipNoise
chop_, 200	qpp::QubitPhaseFlipNoise, 312
display, 199	QuditDepolarizingNoise
IOManipEigen, 199	qpp::QuditDepolarizingNoise, 315
qpp::internal::IOManipPointer	rand
display, 202	rand
end_, 202	qpp, 90–92
IOManipPointer, 201, 202	qpp::Dynamic_bitset, 162, 163
N_, 203	randH
operator=, 202	qpp, 92

randidx	saveMATLAB
qpp, 93	qpp, 101, 102
randket	schatten
qpp, 93	qpp, 102
randkraus	schmidtA
qpp, 93	qpp, 103
randn	schmidtB
qpp, 94, 95	qpp, 103, 104
random.h, 387	schmidtcoeffs
RandomDevices	qpp, 104, 105
qpp::RandomDevices, 318	schmidtprobs
randperm	qpp, 105, 106
qpp, 96	separator
randprime	qpp::internal::IOManipPointer, 203
qpp, 96	qpp::internal::IOManipRange, 206
randprob	set
qpp, 97	
randrho	qpp::Dynamic_bitset, 163, 164
qpp, 97	set_begin_
randU	qpp::QCircuit::iterator, 216
qpp, 97	set_dit
randV	qpp::QEngine, 301
	set_end_
qpp, 98 rd_	qpp::QCircuit::iterator, 216
	set_measured_
qpp::RandomDevices, 320	qpp::QEngine, 301
reference	sigma
qpp::QCircuit::iterator, 214	qpp, 106
renyi	Singleton
qpp, 98, 99	qpp::internal::Singleton, 321, 322
•	
reset	sinm
qpp::Bit_circuit, 132	
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163	sinm
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301	sinm qpp, 107
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301 reshape	sinm qpp, 107 size
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301 reshape qpp, 99	sinm qpp, 107 size qpp::Dynamic_bitset, 164 spectralpowm
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301 reshape qpp, 99 rho2bloch	sinm qpp, 107 size qpp::Dynamic_bitset, 164 spectralpowm qpp, 107
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301 reshape qpp, 99 rho2bloch qpp, 100	sinm qpp, 107 size qpp::Dynamic_bitset, 164 spectralpowm qpp, 107 sqrtm
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301 reshape qpp, 99 rho2bloch qpp, 100 rho2pure	sinm qpp, 107 size qpp::Dynamic_bitset, 164 spectralpowm qpp, 107 sqrtm qpp, 108
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301 reshape qpp, 99 rho2bloch qpp, 100 rho2pure qpp, 100	sinm qpp, 107 size qpp::Dynamic_bitset, 164 spectralpowm qpp, 107 sqrtm qpp, 108 start_
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301 reshape qpp, 99 rho2bloch qpp, 100 rho2pure qpp, 100 Rn	sinm qpp, 107 size qpp::Dynamic_bitset, 164 spectralpowm qpp, 107 sqrtm qpp, 108 start_ qpp::Timer, 341
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301 reshape qpp, 99 rho2bloch qpp, 100 rho2pure qpp, 100 Rn qpp::Gates, 179	sinm
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301 reshape qpp, 99 rho2bloch qpp, 100 rho2pure qpp, 100 Rn	sinm qpp, 107 size qpp::Dynamic_bitset, 164 spectralpowm qpp, 107 sqrtm qpp, 108 start_ qpp::Timer, 341 qpp::internal::IOManipPointer, 203 qpp::internal::IOManipRange, 206
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301 reshape qpp, 99 rho2bloch qpp, 100 rho2pure qpp, 100 Rn qpp::Gates, 179 RX qpp::Gates, 179	sinm qpp, 107 size qpp::Dynamic_bitset, 164 spectralpowm qpp, 107 sqrtm qpp, 108 start_ qpp::Timer, 341 qpp::internal::IOManipPointer, 203 qpp::internal::IOManipRange, 206 States
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301 reshape qpp, 99 rho2bloch qpp, 100 rho2pure qpp, 100 Rn qpp::Gates, 179 RX	sinm
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301 reshape qpp, 99 rho2bloch qpp, 100 rho2pure qpp, 100 Rn qpp::Gates, 179 RX qpp::Gates, 179 RY qpp::Gates, 180	sinm qpp, 107 size qpp::Dynamic_bitset, 164 spectralpowm qpp, 107 sqrtm qpp, 108 start_ qpp::Timer, 341 qpp::internal::IOManipPointer, 203 qpp::internal::IOManipRange, 206 States qpp::States, 328 statistics.h, 388
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301 reshape qpp, 99 rho2bloch qpp, 100 rho2pure qpp, 100 Rn qpp::Gates, 179 RX qpp::Gates, 179 RY	sinm
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301 reshape qpp, 99 rho2bloch qpp, 100 rho2pure qpp, 100 Rn qpp::Gates, 179 RX qpp::Gates, 179 RY qpp::Gates, 180	sinm
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301 reshape qpp, 99 rho2bloch qpp, 100 rho2pure qpp, 100 Rn qpp::Gates, 179 RX qpp::Gates, 179 RY qpp::Gates, 180 RZ qpp::Gates, 180	sinm qpp, 107 size qpp::Dynamic_bitset, 164 spectralpowm qpp, 107 sqrtm qpp, 108 start_ qpp::Timer, 341 qpp::internal::IOManipPointer, 203 qpp::internal::IOManipRange, 206 States qpp::States, 328 statistics.h, 388 step_types_ qpp::QCircuit, 293 StepType
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301 reshape qpp, 99 rho2bloch qpp, 100 rho2pure qpp, 100 Rn qpp::Gates, 179 RX qpp::Gates, 179 RY qpp::Gates, 180 RZ qpp::Gates, 180 S	sinm
<pre>qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301 reshape qpp, 99 rho2bloch qpp, 100 rho2pure qpp, 100 Rn qpp::Gates, 179 RX qpp::Gates, 179 RY qpp::Gates, 180 RZ qpp::Gates, 180 S qpp::Gates, 184</pre>	sinm qpp, 107 size qpp::Dynamic_bitset, 164 spectralpowm qpp, 107 sqrtm qpp, 108 start_ qpp::Timer, 341 qpp::internal::IOManipPointer, 203 qpp::internal::IOManipRange, 206 States qpp::States, 328 statistics.h, 388 step_types_ qpp::QCircuit, 293 StepType qpp::QCircuit, 272 storage_size
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301 reshape qpp, 99 rho2bloch qpp, 100 rho2pure qpp, 100 Rn qpp::Gates, 179 RX qpp::Gates, 179 RY qpp::Gates, 180 RZ qpp::Gates, 180 S qpp::Gates, 184 SWAPd	sinm qpp, 107 size qpp::Dynamic_bitset, 164 spectralpowm qpp, 107 sqrtm qpp, 108 start_ qpp::Timer, 341 qpp::internal::IOManipPointer, 203 qpp::internal::IOManipRange, 206 States qpp::States, 328 statistics.h, 388 step_types_ qpp::QCircuit, 293 StepType qpp::QCircuit, 272 storage_size qpp::Dynamic_bitset, 164
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301 reshape qpp, 99 rho2bloch qpp, 100 rho2pure qpp, 100 Rn qpp::Gates, 179 RX qpp::Gates, 179 RY qpp::Gates, 180 RZ qpp::Gates, 180 S qpp::Gates, 184 SWAPd qpp::Gates, 180	sinm qpp, 107 size qpp::Dynamic_bitset, 164 spectralpowm qpp, 107 sqrtm qpp, 108 start_ qpp::Timer, 341 qpp::internal::IOManipPointer, 203 qpp::internal::IOManipRange, 206 States qpp::States, 328 statistics.h, 388 step_types_ qpp::QCircuit, 293 StepType qpp::QCircuit, 272 storage_size qpp::Dynamic_bitset, 164 storage_size_
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301 reshape qpp, 99 rho2bloch qpp, 100 rho2pure qpp, 100 Rn qpp::Gates, 179 RX qpp::Gates, 179 RY qpp::Gates, 180 RZ qpp::Gates, 180 S qpp::Gates, 184 SWAPd qpp::Gates, 180 SWAP	sinm qpp, 107 size qpp::Dynamic_bitset, 164 spectralpowm qpp, 107 sqrtm qpp, 108 start_ qpp::Timer, 341 qpp::internal::IOManipPointer, 203 qpp::internal::IOManipRange, 206 States qpp::States, 328 statistics.h, 388 step_types_ qpp::QCircuit, 293 StepType qpp::QCircuit, 272 storage_size qpp::Dynamic_bitset, 164 storage_size_ qpp::Dynamic_bitset, 165
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301 reshape qpp, 99 rho2bloch qpp, 100 rho2pure qpp, 100 Rn qpp::Gates, 179 RX qpp::Gates, 179 RY qpp::Gates, 180 RZ qpp::Gates, 180 S qpp::Gates, 180 S qpp::Gates, 180 SWAP qpp::Bit_circuit, 133	sinm qpp, 107 size qpp::Dynamic_bitset, 164 spectralpowm qpp, 107 sqrtm qpp, 108 start_ qpp::Timer, 341 qpp::internal::IOManipPointer, 203 qpp::internal::IOManipRange, 206 States qpp::States, 328 statistics.h, 388 step_types_ qpp::QCircuit, 293 StepType qpp::QCircuit, 272 storage_size qpp::Dynamic_bitset, 164 storage_size_ qpp::Dynamic_bitset, 165 storage_type
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301 reshape qpp, 99 rho2bloch qpp, 100 rho2pure qpp, 100 Rn qpp::Gates, 179 RX qpp::Gates, 179 RY qpp::Gates, 180 RZ qpp::Gates, 180 S qpp::Gates, 180 S S qpp::Gates, 180 SWAP qpp::Bit_circuit, 133 qpp::Bit_circuit::Gate_count, 171	sinm qpp, 107 size qpp::Dynamic_bitset, 164 spectralpowm qpp, 107 sqrtm qpp, 108 start_ qpp::Timer, 341 qpp::internal::IOManipPointer, 203 qpp::internal::IOManipRange, 206 States qpp::States, 328 statistics.h, 388 step_types_ qpp::QCircuit, 293 StepType qpp::QCircuit, 272 storage_size qpp::Dynamic_bitset, 164 storage_type qpp::Dynamic_bitset, 165 storage_type qpp::Dynamic_bitset, 157
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301 reshape qpp, 99 rho2bloch qpp, 100 rho2pure qpp, 100 Rn qpp::Gates, 179 RX qpp::Gates, 179 RY qpp::Gates, 180 RZ qpp::Gates, 180 S qpp::Gates, 180 S qpp::Gates, 180 SWAP qpp::Bit_circuit, 133	sinm qpp, 107 size qpp::Dynamic_bitset, 164 spectralpowm qpp, 107 sqrtm qpp, 108 start_ qpp::Timer, 341 qpp::internal::IOManipPointer, 203 qpp::internal::IOManipRange, 206 States qpp::States, 328 statistics.h, 388 step_types_ qpp::QCircuit, 293 StepType qpp::QCircuit, 272 storage_size qpp::Dynamic_bitset, 164 storage_size_ qpp::Dynamic_bitset, 165 storage_type qpp::Dynamic_bitset, 157 subsys_
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301 reshape qpp, 99 rho2bloch qpp, 100 rho2pure qpp, 100 Rn qpp::Gates, 179 RX qpp::Gates, 179 RY qpp::Gates, 180 RZ qpp::Gates, 180 S qpp::Gates, 180 S S qpp::Gates, 180 SWAP qpp::Bit_circuit, 133 qpp::Bit_circuit::Gate_count, 171	sinm qpp, 107 size qpp::Dynamic_bitset, 164 spectralpowm qpp, 107 sqrtm qpp, 108 start_ qpp::Timer, 341 qpp::internal::IOManipPointer, 203 qpp::internal::IOManipRange, 206 States qpp::States, 328 statistics.h, 388 step_types_ qpp::QCircuit, 293 StepType qpp::QCircuit, 272 storage_size qpp::Dynamic_bitset, 164 storage_type qpp::Dynamic_bitset, 165 storage_type qpp::Dynamic_bitset, 157
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301 reshape qpp, 99 rho2bloch qpp, 100 rho2pure qpp, 100 Rn qpp::Gates, 179 RX qpp::Gates, 179 RY qpp::Gates, 180 RZ qpp::Gates, 180 S qpp::Gates, 180 S qpp::Gates, 180 S s qpp::Gates, 180 SWAP qpp::Bit_circuit, 133 qpp::Bit_circuit::Gate_count, 171 qpp::Gates, 184 save qpp, 101	sinm qpp, 107 size qpp::Dynamic_bitset, 164 spectralpowm qpp, 107 sqrtm qpp, 108 start_ qpp::Timer, 341 qpp::internal::IOManipPointer, 203 qpp::internal::IOManipRange, 206 States qpp::States, 328 statistics.h, 388 step_types_ qpp::QCircuit, 293 StepType qpp::QCircuit, 272 storage_size qpp::Dynamic_bitset, 164 storage_size_ qpp::Dynamic_bitset, 165 storage_type qpp::Dynamic_bitset, 157 subsys_
qpp::Bit_circuit, 132 qpp::Dynamic_bitset, 163 qpp::QEngine, 301 reshape qpp, 99 rho2bloch qpp, 100 rho2pure qpp, 100 Rn qpp::Gates, 179 RX qpp::Gates, 179 RY qpp::Gates, 180 RZ qpp::Gates, 180 S qpp::Gates, 180 S qpp::Gates, 180 S s qpp::Gates, 180 SWAPd qpp::Gates, 180 SWAP qpp::Bit_circuit, 133 qpp::Bit_circuit::Gate_count, 171 qpp::Gates, 184 save	sinm qpp, 107 size qpp::Dynamic_bitset, 164 spectralpowm qpp, 107 sqrtm qpp, 108 start_ qpp::Timer, 341 qpp::internal::IOManipPointer, 203 qpp::internal::IOManipRange, 206 States qpp::States, 328 statistics.h, 388 step_types_ qpp::QCircuit, 293 StepType qpp::QCircuit, 272 storage_size qpp::Dynamic_bitset, 164 storage_size_ qpp::Dynamic_bitset, 165 storage_type qpp::Dynamic_bitset, 157 subsys_ qpp::QEngine, 303

super2choi	qpp::exception::DimsMismatchRvector, 147
qpp, 109	qpp::exception::DimsMismatchVector, 149
svals	qpp::exception::DimsNotEqual, 151
qpp, 110	qpp::exception::Duplicates, 154
svd	qpp::exception::Exception, 169
qpp, 110	qpp::exception::InvalidIterator, 197
svdU	qpp::exception::MatrixMismatchSubsys, 220
qpp, 110	qpp::exception::MatrixNotCvector, 222
svdV	qpp::exception::MatrixNotRvector, 224
qpp, 111	qpp::exception::MatrixNotSquare, 226
syspermute	qpp::exception::MatrixNotSquareNorCvector, 228
gpp, 111, 112	qpp::exception::MatrixNotSquareNorRvector, 230
ΥΡΡ , 1111, 112	
Т	qpp::exception::MatrixNotSquareNorVector, 232
	qpp::exception::MatrixNotVector, 234
qpp::Gates, 184	qpp::exception::NoCodeword, 239
TFQ	qpp::exception::NotBipartite, 248
qpp, 112	qpp::exception::NotImplemented, 250
qpp::QCircuit, 289	qpp::exception::NotQubitCvector, 252
TOF	
qpp::Bit_circuit, 133	qpp::exception::NotQubitMatrix, 254
	qpp::exception::NotQubitRvector, 256
qpp::Bit_circuit::Gate_count, 171	qpp::exception::NotQubitSubsys, 258
qpp::Gates, 184	qpp::exception::NotQubitVector, 260
target_	qpp::exception::OutOfRange, 262
qpp::QCircuit::GateStep, 187	qpp::exception::PermInvalid, 264
qpp::QCircuit::MeasureStep, 237	
tic	qpp::exception::PermMismatchDims, 266
	qpp::exception::QuditAlreadyMeasured, 314
qpp::Timer, 340	qpp::exception::SizeMismatch, 324
tics	qpp::exception::SubsysMismatchDims, 336
qpp::Timer, 341	qpp::exception::TypeMismatch, 344
Timer	
qpp::Timer, 338, 339	qpp::exception::UndefinedType, 346
to_JSON	qpp::exception::Unknown, 348
	qpp::exception::ZeroSize, 353
qpp::IJSON, 193	types.h, 391
qpp::QCircuit, 289	
qpp::QEngine, 302	uniform
to_string	qpp, 114
qpp::Dynamic_bitset, 164	APP, TTT
to_void	V
	V_
qpp, 28	qpp::Dynamic_bitset, 165
toc	value_type
qpp::Timer, 341	qpp::Dynamic_bitset, 157
trace	qpp::QCircuit::iterator, 214
qpp, 112	value_type_
traits.h, 389	qpp::QCircuit::iterator::value_type_, 349
transpose	value_type_qc_
qpp, 113	<pre>qpp::QCircuit::iterator::value_type_, 351</pre>
tsallis	var
qpp, 113, 114	qpp, 115
Type	variadic_vector_emplace
qpp::Codes, 135	qpp::internal, 124
	qppinternat, 124
type	14/
qpp::make_void, 218	W
type_	qpp::States, 333
<pre>qpp::QCircuit::iterator::value_type_, 351</pre>	what
type_description	qpp::exception::Exception, 169
qpp::exception::CustomException, 139	what_
qpp::exception::DimsInvalid, 141	
	qpp::exception::CustomException, 139
qpp::exception::DimsMismatchCvector, 143	where_
qpp::exception::DimsMismatchMatrix, 145	qpp::exception::Exception, 170

```
Χ
     qpp::Bit_circuit, 133
    qpp::Bit_circuit::Gate_count, 171
     qpp::Gates, 184
х0
    qpp::States, 333
x1
     qpp::States, 334
x2contfrac
    qpp, 115
Χd
    qpp::Gates, 182
Υ
     qpp::Gates, 185
y0
    qpp::States, 334
у1
    qpp::States, 334
Ζ
    qpp::Gates, 185
z0
    qpp::States, 334
z1
    qpp::States, 334
Zd
    qpp::Gates, 182
zero
    qpp::States, 330
```