Quantum++ v1.2

Generated by Doxygen 1.8.14

Contents

1	Qua	ntum++																	1
2	Nam	nespace	Index																3
	2.1	Names	space List					 	 	 	 	 		 				 	3
3	Hier	archica	l Index																5
	3.1	Class I	Hierarchy					 	 	 		 	 	 				 	5
4	Clas	s Index																	9
	4.1	Class I	List					 	 	 		 		 				 	9
5	File	Index																	13
	5.1	File Lis	st					 	 	 		 		 				 	13
6	Nam	nespace	Docume	ntat	tion														15
	6.1	qpp Na	amespace	Ref	ferer	тсе		 	 	 		 		 				 	15
		6.1.1	Detailed	Des	scrip	tion		 	 	 		 		 				 	28
		6.1.2	Typedef	Doc	cume	entat	ion	 	 	 		 		 				 	28
			6.1.2.1	bi	gint			 	 			 		 				 	28
			6.1.2.2	br	a.			 	 	 		 		 				 	29
			6.1.2.3	cr	nat			 	 	 		 	 	 				 	29
			6.1.2.4	cp	olx .			 	 			 		 				 	29
			6.1.2.5	dr	mat			 	 	 		 		 				 	29
			6.1.2.6	dy	yn_c	ol_ve	ect	 	 		 -	 		 			•	 	29
			6.1.2.7	dy	yn_m	nat		 	 			 		 				 	30
			6.1.2.8	dy	yn_rc	ow_v	/ect		 	 		 		 				 	30

ii CONTENTS

	6.1.2.9	idx	30
	6.1.2.10	ket	30
	6.1.2.11	to_void	31
6.1.3	Function	Documentation	31
	6.1.3.1	absm()	31
	6.1.3.2	abssq() [1/3]	31
	6.1.3.3	abssq() [2/3]	32
	6.1.3.4	abssq() [3/3]	32
	6.1.3.5	adjoint()	32
	6.1.3.6	anticomm()	33
	6.1.3.7	apply() [1/5]	33
	6.1.3.8	apply() [2/5]	34
	6.1.3.9	apply() [3/5]	34
	6.1.3.10	apply() [4/5]	35
	6.1.3.11	apply() [5/5]	35
	6.1.3.12	applyCTRL() [1/2]	36
	6.1.3.13	applyCTRL() [2/2]	37
	6.1.3.14	applyQFT()	37
	6.1.3.15	applyTFQ()	38
	6.1.3.16	avg()	38
	6.1.3.17	bloch2rho()	39
	6.1.3.18	choi2kraus()	39
	6.1.3.19	choi2super()	40
	6.1.3.20	comm()	40
	6.1.3.21	complement()	41
	6.1.3.22	compperm()	41
	6.1.3.23	concurrence()	41
	6.1.3.24	conjugate()	42
	6.1.3.25	contfrac2x()	42
	6.1.3.26	convergents() [1/2]	43

6.1.3.27	convergents() [2/2]	43
6.1.3.28	cor()	44
6.1.3.29	cosm()	44
6.1.3.30	cov()	44
6.1.3.31	cwise()	45
6.1.3.32	det()	45
6.1.3.33	dirsum() [1/4]	46
6.1.3.34	dirsum() [2/4]	46
6.1.3.35	dirsum() [3/4]	47
6.1.3.36	dirsum() [4/4]	47
6.1.3.37	dirsumpow()	47
6.1.3.38	disp() [1/5]	48
6.1.3.39	disp() [2/5]	48
6.1.3.40	disp() [3/5]	49
6.1.3.41	disp() [4/5]	49
6.1.3.42	disp() [5/5]	50
6.1.3.43	egcd()	50
6.1.3.44	eig()	51
6.1.3.45	entanglement() [1/2]	51
6.1.3.46	entanglement() [2/2]	52
6.1.3.47	entropy() [1/2]	52
6.1.3.48	entropy() [2/2]	53
6.1.3.49	evals()	53
6.1.3.50	evects()	53
6.1.3.51	expm()	54
6.1.3.52	factors()	54
6.1.3.53	funm()	55
6.1.3.54	gcd() [1/2]	55
6.1.3.55	gcd() [2/2]	56
6.1.3.56	gconcurrence()	56

iv CONTENTS

6.1.3.57	grams() [1/3]	57
6.1.3.58	grams() [2/3]	57
6.1.3.59	grams() [3/3]	57
6.1.3.60	hash_eigen()	58
6.1.3.61	heig()	58
6.1.3.62	hevals()	59
6.1.3.63	hevects()	59
6.1.3.64	inverse()	60
6.1.3.65	invperm()	60
6.1.3.66	ip() [1/2]	60
6.1.3.67	ip() [2/2]	61
6.1.3.68	isprime()	61
6.1.3.69	kraus2choi()	62
6.1.3.70	kraus2super()	62
6.1.3.71	kron() [1/4]	63
6.1.3.72	kron() [2/4]	63
6.1.3.73	kron() [3/4]	64
6.1.3.74	kron() [4/4]	64
6.1.3.75	kronpow()	64
6.1.3.76	lcm() [1/2]	65
6.1.3.77	lcm() [2/2]	65
6.1.3.78	load()	66
6.1.3.79	loadMATLAB() [1/2]	66
6.1.3.80	loadMATLAB() [2/2]	67
6.1.3.81	logdet()	68
6.1.3.82	logm()	68
6.1.3.83	lognegativity() [1/2]	69
6.1.3.84	lognegativity() [2/2]	69
6.1.3.85	marginalX()	69
6.1.3.86	marginalY()	71

6.1.3.87 measure() [1/9]
6.1.3.88 measure() [2/9]
6.1.3.89 measure() [3/9]
6.1.3.90 measure() [4/9]
6.1.3.91 measure() [5/9]
6.1.3.92 measure() [6/9]
6.1.3.93 measure() [7/9]
6.1.3.94 measure() [8/9]
6.1.3.95 measure() [9/9]
6.1.3.96 measure_seq() [1/2]
6.1.3.97 measure_seq() [2/2]
6.1.3.98 mket() [1/2]
6.1.3.99 mket() [2/2]
6.1.3.100 modinv()
6.1.3.101 modmul()
6.1.3.102 modpow()
6.1.3.103 mprj() [1/2]
6.1.3.104 mprj() [2/2]
6.1.3.105 multiidx2n()
6.1.3.106 n2multiidx()
6.1.3.107 negativity() [1/2]
6.1.3.108 negativity() [2/2]
6.1.3.109 norm()
6.1.3.110 normalize()
6.1.3.111 omega()
6.1.3.112 operator""""i()
6.1.3.113 powm()
6.1.3.114 prj()
6.1.3.115 prod() [1/3]
6.1.3.116 prod() [2/3]

vi

6.1.3.117 prod() [3/3]	36
6.1.3.118 ptrace() [1/2] 8	36
6.1.3.119 ptrace() [2/2] 8	37
6.1.3.120 ptrace1() [1/2] 8	37
6.1.3.121 ptrace1() [2/2]	38
6.1.3.122 ptrace2() [1/2]	38
6.1.3.123 ptrace2() [2/2] 8	39
6.1.3.124 ptranspose() [1/2]	39
6.1.3.125 ptranspose() [2/2]	90
6.1.3.126 QFT()	90
6.1.3.127 qmutualinfo() [1/2] 9	91
6.1.3.128 qmutualinfo() [2/2]	91
6.1.3.129 rand() [1/5]	92
6.1.3.130 rand() [2/5] 9	92
6.1.3.131 rand() [3/5]	93
6.1.3.132 rand() [4/5]	93
6.1.3.133 rand() [5/5]	94
6.1.3.134 randH()	94
6.1.3.135 randidx()	95
6.1.3.136 randket()	95
6.1.3.137 randkraus()	95
6.1.3.138 randn() [1/4] 9	96
6.1.3.139 randn() [2/4] 9	96
6.1.3.140 randn() [3/4] 9	97
6.1.3.141 randn() [4/4] S	97
6.1.3.142 randperm()	98
6.1.3.143 randprime()	98
6.1.3.144 randprob()	99
6.1.3.145 randrho()	99
6.1.3.146 randU()	99

CONTENTS vii

6.1.3.147 randV()
6.1.3.148 renyi() [1/2]
6.1.3.149 renyi() [2/2]
6.1.3.150 reshape()
6.1.3.151 rho2bloch()
6.1.3.152 rho2pure()
6.1.3.153 save()
6.1.3.154 saveMATLAB() [1/2]
6.1.3.155 saveMATLAB() [2/2]
6.1.3.156 schatten()
6.1.3.157 schmidtA() [1/2]
6.1.3.158 schmidtA() [2/2]
6.1.3.159 schmidtB() [1/2]
6.1.3.160 schmidtB() [2/2]
6.1.3.161 schmidtcoeffs() [1/2]
6.1.3.162 schmidtcoeffs() [2/2] 107
6.1.3.163 schmidtprobs() [1/2]
6.1.3.164 schmidtprobs() [2/2]
6.1.3.165 sigma()
6.1.3.166 sinm()
6.1.3.167 spectralpowm()
6.1.3.168 sqrtm()
6.1.3.169 sum() [1/3]
6.1.3.170 sum() [2/3]
6.1.3.171 sum() [3/3]
6.1.3.172 super2choi()
6.1.3.173 svals()
6.1.3.174 svd()
6.1.3.175 svdU()
6.1.3.176 svdV()

viii CONTENTS

		6.1.3.177	syspermute() [1/2]		 	 	 	 	113
		6.1.3.178	syspermute() [2/2]		 	 	 	 	114
		6.1.3.179	TFQ()		 	 	 	 	114
		6.1.3.180	trace()		 	 	 	 	115
		6.1.3.181	transpose()		 	 	 	 	115
		6.1.3.182	tsallis() [1/2]		 	 	 	 	115
		6.1.3.183	tsallis() [2/2]		 	 	 	 	116
		6.1.3.184	uniform()		 	 	 	 	116
		6.1.3.185	var()		 	 	 	 	117
		6.1.3.186	x2contfrac()		 	 	 	 	117
	6.1.4	Variable	Occumentation		 	 	 	 	118
		6.1.4.1	chop		 	 	 	 	118
		6.1.4.2	ee		 	 	 	 	118
		6.1.4.3	infty		 	 	 	 	118
		6.1.4.4	maxn		 	 	 	 	118
		6.1.4.5	pi		 	 	 	 	118
6.2	qpp::ex	ception N	mespace Reference		 	 	 	 	118
	6.2.1	Detailed	Description		 	 	 	 	120
6.3	qpp::ex	perimenta	Namespace Reference		 	 	 	 	120
	6.3.1	Detailed	Description		 	 	 	 	120
6.4	qpp::int	ternal Nan	espace Reference		 	 	 	 	120
	6.4.1	Detailed	Description		 	 	 	 	122
	6.4.2	Function	Documentation		 	 	 	 	122
		6.4.2.1	check_cvector()		 	 	 	 	122
		6.4.2.2	check_dims()		 	 	 	 	122
		6.4.2.3	check_dims_match_cve	ct()	 	 	 	 	122
		6.4.2.4	check_dims_match_mat	:()	 	 	 	 	122
		6.4.2.5	check_dims_match_rved	ct()	 	 	 	 	123
		6.4.2.6	check_eq_dims()		 	 	 	 	123
		6.4.2.7	check_matching_sizes()		 	 	 	 	123

		6.4.2.8	check_no_duplicates()	23
		6.4.2.9	check_nonzero_size()	23
		6.4.2.10	check_perm()	23
		6.4.2.11	check_qubit_cvector()	24
		6.4.2.12	check_qubit_matrix()	24
		6.4.2.13	check_qubit_rvector()	24
		6.4.2.14	check_qubit_vector()	24
		6.4.2.15	check_rvector()	24
		6.4.2.16	check_square_mat()	24
		6.4.2.17	check_subsys_match_dims()	25
		6.4.2.18	check_vector()	25
		6.4.2.19	dirsum2()	25
		6.4.2.20	get_dim_subsys()	25
		6.4.2.21	get_num_subsys()	25
		6.4.2.22	hash_combine()	25
		6.4.2.23	kron2()	26
		6.4.2.24	multiidx2n()	26
		6.4.2.25	n2multiidx()	26
		6.4.2.26	variadic_vector_emplace() [1/2]	26
		6.4.2.27	variadic_vector_emplace() [2/2]	26
6.5	qpp::lit	erals Nam	espace Reference	27
	6.5.1	Function	Documentation	27
		6.5.1.1	operator""""_bra()	27
		6.5.1.2	operator""""_i()	27
		6.5.1.3	operator"""" _ket()	28
		6.5.1.4	operator"""" _prj()	28

7	Clas	s Docu	mentation	131
	7.1	qpp::Bi	t_circuit Class Reference	131
		7.1.1	Detailed Description	133
		7.1.2	Constructor & Destructor Documentation	133
			7.1.2.1 Bit_circuit() [1/2]	133
			7.1.2.2 Bit_circuit() [2/2]	133
		7.1.3	Member Function Documentation	134
			7.1.3.1 CNOT()	134
			7.1.3.2 FRED()	134
			7.1.3.3 NOT()	135
			7.1.3.4 reset()	135
			7.1.3.5 SWAP()	135
			7.1.3.6 TOF()	136
			7.1.3.7 X()	136
		7.1.4	Member Data Documentation	136
			7.1.4.1 gate_count	137
			7.1.4.2 this	137
	7.2	qpp::C	odes Class Reference	137
		7.2.1	Detailed Description	138
		7.2.2	Member Enumeration Documentation	138
			7.2.2.1 Type	138
		7.2.3	Constructor & Destructor Documentation	139
			7.2.3.1 Codes()	139
			7.2.3.2 ~Codes()	139
		7.2.4	Member Function Documentation	139
			7.2.4.1 codeword()	139
		7.2.5	Friends And Related Function Documentation	139
			7.2.5.1 internal::Singleton < const Codes >	140
	7.3	qpp::ex	cception::CustomException Class Reference	140
		7.3.1	Detailed Description	141

CONTENTS xi

	7.3.2	Construc	ctor & Destructor Documentation	141
		7.3.2.1	CustomException()	142
	7.3.3	Member	Function Documentation	142
		7.3.3.1	type_description()	142
	7.3.4	Member	Data Documentation	142
		7.3.4.1	what	142
7.4	qpp::ex	xception::[DimsInvalid Class Reference	143
	7.4.1	Detailed	Description	144
	7.4.2	Member	Function Documentation	144
		7.4.2.1	Exception()	144
		7.4.2.2	type_description()	144
7.5	qpp::ex	xception::[DimsMismatchCvector Class Reference	145
	7.5.1	Detailed	Description	146
	7.5.2	Member	Function Documentation	146
		7.5.2.1	Exception()	146
		7.5.2.2	type_description()	146
7.6	qpp::ex	xception::[DimsMismatchMatrix Class Reference	. 147
	7.6.1	Detailed	Description	148
	7.6.2	Member	Function Documentation	148
		7.6.2.1	Exception()	148
		7.6.2.2	type_description()	148
7.7	qpp::ex	xception::[DimsMismatchRvector Class Reference	149
	7.7.1	Detailed	Description	150
	7.7.2	Member	Function Documentation	150
		7.7.2.1	Exception()	150
		7.7.2.2	type_description()	150
7.8	qpp::ex	xception::[DimsMismatchVector Class Reference	151
	7.8.1	Detailed	Description	152
	7.8.2	Member	Function Documentation	152
		7.8.2.1	Exception()	152

xii CONTENTS

		7.8.2.2	type_description()	 	 152
7.9	qpp::ex	ception::E	DimsNotEqual Class Reference	 	 153
	7.9.1	Detailed	Description	 	 154
	7.9.2	Member	Function Documentation	 	 154
		7.9.2.1	Exception()	 	 154
		7.9.2.2	type_description()	 	 154
7.10	qpp::int	ternal::Dis	splay_Impl_ Struct Reference	 	 155
	7.10.1	Member	Function Documentation	 	 155
		7.10.1.1	display_impl_()	 	 155
7.11	qpp::ex	ception::E	Duplicates Class Reference	 	 156
	7.11.1	Detailed	Description	 	 157
	7.11.2	Member	Function Documentation	 	 157
		7.11.2.1	Exception()	 	 157
		7.11.2.2	type_description()	 	 157
7.12	qpp::Dy	ynamic_bi	itset Class Reference	 	 158
	7.12.1	Detailed	Description	 	 160
	7.12.2	Member	Typedef Documentation	 	 160
		7.12.2.1	storage_type	 	 160
		7.12.2.2	value_type	 	 160
	7.12.3	Construc	ctor & Destructor Documentation	 	 160
		7.12.3.1	Dynamic_bitset()	 	 160
		7.12.3.2	~Dynamic_bitset()	 	 161
	7.12.4	Member	Function Documentation	 	 161
		7.12.4.1	all()	 	 161
		7.12.4.2	any()	 	 161
		7.12.4.3	count()	 	 161
		7.12.4.4	data()	 	 162
		7.12.4.5	display()	 	 162
		7.12.4.6	flip() [1/2]	 	 162
		7.12.4.7	flip() [2/2]	 	 163

CONTENTS xiii

		7.12.4.8 get()	63
		7.12.4.9 index_()	63
		7.12.4.10 none()	64
		7.12.4.11 offset_()	64
		7.12.4.12 operator"!=()	64
		7.12.4.13 operator-()	65
		7.12.4.14 operator==()	65
		7.12.4.15 rand() [1/2]	65
		7.12.4.16 rand() [2/2]	66
		7.12.4.17 reset() [1/2]	66
		7.12.4.18 reset() [2/2]	66
		7.12.4.19 set() [1/2]	67
		7.12.4.20 set() [2/2]	67
		7.12.4.21 size()	67
		7.12.4.22 storage_size()	67
		7.12.4.23 to_string()	68
	7.12.5	Member Data Documentation	68
		7.12.5.1 n	68
		7.12.5.2 storage_size	68
		7.12.5.3 v	69
7.13	qpp::in	ternal::EqualEigen Class Reference	69
	7.13.1	Detailed Description	69
	7.13.2	Member Function Documentation	69
		7.13.2.1 operator()()	69
7.14	qpp::ex	cception::Exception Class Reference	70
	7.14.1	Detailed Description	71
	7.14.2	Constructor & Destructor Documentation	72
		7.14.2.1 Exception()	72
	7.14.3	Member Function Documentation	72
		7.14.3.1 type_description()	72

xiv CONTENTS

	7	7.14.3.2	۷	wha	at()									 			 			 	 	173
7.	14.4 N	Member [Da	ata	ι Do	cum	ıen	ıtat	tion	١				 			 			 	 	173
	7	7.14.4.1	n	ms	g_									 			 			 	 	173
	7	7.14.4.2	٧	whe	ere_	_ • •								 			 			 	 	173
7.15 qp	p::Bit_	circuit::G	Ga	ıte_	_col	unt (Cla	SS	Re	efer	end	ce.		 			 			 	 	173
7.	15.1 E	Detailed [De	esc	cript	ion								 			 			 	 	174
7.	15.2 N	Member F	Fι	unc	ction	ı Do	cur	me	enta	atio	n			 			 			 	 	174
	7	7.15.2.1	r	res	et()									 			 			 	 	174
7.	15.3 N	Member [Da	ata	ι Do	cum	ıen	ıtat	tion	١				 			 			 	 	174
	7	7.15.3.1	(CN	ОТ									 			 			 	 	174
	7	7.15.3.2	F	FRI	ED									 			 			 	 	174
	7	7.15.3.3	N	NO	т									 			 			 	 	174
	7	7.15.3.4	5	SW	/AP									 			 			 	 	174
	7	7.15.3.5	1	то	F									 			 			 	 	175
	7	7.15.3.6	t	ota	al									 			 			 	 	175
	7	7.15.3.7	>	Χ.										 			 			 	 	175
7.16 qp	op::Bit_	circuit::G	Ga	ıte_	_de	oth (Cla	เรร	Re	efer	end	се		 			 			 	 	175
7.	16.1 E	Detailed [De	esc	cript	ion								 			 			 	 	177
7.	16.2	Construct	cto	ır &	ι De	stru	ıcto	or E	Doc	cum	nen	ıtati	on	 			 			 	 	177
	7	7.16.2.1	C	Gat	te_c	tqət	h()	[1	1/3]				 			 			 	 	177
	7	7.16.2.2	C	Gat	te_c	dept	h()	[2	2/3]				 			 			 	 	177
	7	7.16.2.3	C	Gat	te_c	dept	h()	[3	3/3]				 			 			 	 	178
7.	16.3 N	Member F	Fι	unc	ction	ı Do	cur	me	enta	atio	n			 			 			 	 	178
	7	7.16.3.1	C	ope	erato	or=() .							 			 			 	 	178
	7	7.16.3.2	r	res	et()									 			 			 	 	178
7.	16.4 N	Member [Da	ata	ι Do	cum	nen	ıtat	tion	ı				 			 			 	 	178
	7	7.16.4.1	b	ъCI	NO ⁻	Γ.,								 			 			 	 	178
	7	7.16.4.2	b	oFF	REC) .								 			 			 	 	179
	7	7.16.4.3	E	Bit_	_cird	cuit .								 			 			 	 	179
	7	7.16.4.4	b	oit_	_circ	:uit_								 			 			 	 	179

CONTENTS xv

	7.16.4.5 bNOT	179
	7.16.4.6 bSWAP	179
	7.16.4.7 bTOF	179
	7.16.4.8 btotal	179
	7.16.4.9 CNOT	179
	7.16.4.10 FRED	180
	7.16.4.11 NOT	180
	7.16.4.12 SWAP	180
	7.16.4.13 TOF	180
	7.16.4.14 total	180
	7.16.4.15 X	180
7.17 qpp::G	ates Class Reference	181
7.17.1	Detailed Description	183
7.17.2	Constructor & Destructor Documentation	183
	7.17.2.1 Gates()	183
	7.17.2.2 ~Gates()	183
7.17.3	Member Function Documentation	184
	7.17.3.1 CTRL()	184
	7.17.3.2 expandout() [1/3]	184
	7.17.3.3 expandout() [2/3]	185
	7.17.3.4 expandout() [3/3]	186
	7.17.3.5 Fd()	186
	7.17.3.6 get_name()	187
	7.17.3.7 ld()	187
	7.17.3.8 MODMUL()	187
	7.17.3.9 Rn()	188
	7.17.3.10 RX()	188
	7.17.3.11 RY()	189
	7.17.3.12 RZ()	189
	7.17.3.13 SWAPd()	189

xvi CONTENTS

		7.17.3.14 Xd()	91
		7.17.3.15 Zd()	91
	7.17.4	Friends And Related Function Documentation	92
		7.17.4.1 internal::Singleton < const Gates >	92
	7.17.5	Member Data Documentation	92
		7.17.5.1 CNOT	92
		7.17.5.2 CNOTba	92
		7.17.5.3 CZ	92
		7.17.5.4 FRED	92
		7.17.5.5 H	93
		7.17.5.6 ld2	93
		7.17.5.7 S	93
		7.17.5.8 SWAP	93
		7.17.5.9 T	93
		7.17.5.10 TOF	93
		7.17.5.11 X	94
		7.17.5.12 Y	94
		7.17.5.13 Z	94
7.18	qpp::Q	Circuit::GateStep Struct Reference	94
	7.18.1	Detailed Description	95
	7.18.2	Constructor & Destructor Documentation	95
		7.18.2.1 GateStep() [1/2]	95
		7.18.2.2 GateStep() [2/2]	95
	7.18.3	Member Data Documentation	96
		7.18.3.1 ctrl	96
		7.18.3.2 gate_hash	96
		7.18.3.3 gate_type	96
		7.18.3.4 name	96
		7.18.3.5 target	97
7.19	qpp::int	ternal::HashEigen Class Reference	97

CONTENTS xvii

	7.19.1	Detailed Description	197
	7.19.2	Member Function Documentation	197
		7.19.2.1 operator()()	197
7.20	qpp::ID	isplay Class Reference	198
	7.20.1	Detailed Description	199
	7.20.2	Constructor & Destructor Documentation	199
		7.20.2.1 IDisplay() [1/3]	199
		7.20.2.2 IDisplay() [2/3]	199
		7.20.2.3	199
		7.20.2.4 ~IDisplay()	199
	7.20.3	Member Function Documentation	200
		7.20.3.1 display()	200
		7.20.3.2 operator=() [1/2]	200
		7.20.3.3 operator=() [2/2]	200
	7.20.4	Friends And Related Function Documentation	200
		7.20.4.1 operator<<	200
7.21	qpp::lJ\$	SON Class Reference	201
	7.21.1	Detailed Description	201
	7.21.2	Constructor & Destructor Documentation	202
		7.21.2.1 IJSON() [1/3]	202
		7.21.2.2 IJSON() [2/3]	202
		7.21.2.3 IJSON() [3/3]	202
		7.21.2.4 ~IJSON()	202
	7.21.3	Member Function Documentation	202
		7.21.3.1 operator=() [1/2]	202
		7.21.3.2 operator=() [2/2]	203
		7.21.3.3 to_JSON()	203
7.22	qpp::lni	t Class Reference	203
	7.22.1	Detailed Description	204
	7.22.2	Constructor & Destructor Documentation	204

xviii CONTENTS

7.22.2.1 Init()	204
7.22.2.2 ~Init()	205
7.22.3 Friends And Related Function Documentation	205
7.22.3.1 internal::Singleton< const Init >	205
7.23 qpp::exception::InvalidIterator Class Reference	205
7.23.1 Detailed Description	206
7.23.2 Member Function Documentation	206
7.23.2.1 Exception()	206
7.23.2.2 type_description()	207
7.24 qpp::internal::IOManipEigen Class Reference	207
7.24.1 Constructor & Destructor Documentation	208
7.24.1.1 IOManipEigen() [1/2]	208
7.24.1.2 IOManipEigen() [2/2]	209
7.24.2 Member Function Documentation	209
7.24.2.1 display()	209
7.24.3 Member Data Documentation	209
7.24.3.1 A	209
7.24.3.2 chop	209
7.25 qpp::internal::IOManipPointer< PointerType > Class Template Reference	210
7.25.1 Constructor & Destructor Documentation	211
7.25.1.1 IOManipPointer() [1/2]	211
7.25.1.2 IOManipPointer() [2/2]	211
7.25.2 Member Function Documentation	211
7.25.2.1 display()	211
7.25.2.2 operator=()	212
7.25.3 Member Data Documentation	212
7.25.3.1 end	212
7.25.3.2 N	212
7.25.3.3 p	212
7.25.3.4 separator	212

CONTENTS xix

		7.25.3.5	sta	ırt											 	 	 	 212
7.26	qpp::in	ternal::IOM	Mani	pRanç	је<	Inpu	utlter	rator	> C	lass	Temp	late	Refer	ence	 	 	 	 213
	7.26.1	Construct	ctor 8	& Dest	ructo	or D	ocur)	menta	ation						 	 	 	 214
		7.26.1.1	Ю	Manip	Ranç	ge()	[1/	2] .							 	 	 	 214
		7.26.1.2	Ю	Manip	Ranç	ge()	[2/	2] .							 	 	 	 214
	7.26.2	Member I	Fun	ction [Docu	ımer	ntatio	on	 214
		7.26.2.1	dis	splay()											 	 	 	 214
		7.26.2.2	op	erator:	=() .										 	 	 	 215
	7.26.3	Member I	Data	a Doci	umen	ntatio	on .								 	 	 	 215
		7.26.3.1	en	d											 	 	 	 215
		7.26.3.2	firs	st											 	 	 	 215
		7.26.3.3	las	it											 	 	 	 215
		7.26.3.4	se	parato	r										 	 	 	 215
		7.26.3.5	sta	ırt											 	 	 	 215
7.27	qpp::is_	_complex<	< T	> Stru	uct Te	emp	olate	Refe	erenc	e.					 	 	 	 216
	7.27.1	Detailed I	Des	criptio	n .										 	 	 	 216
7.28	qpp::is_	_complex<	< st	d::com	ıplex	< T	Γ>>	> Str	uct T	emp	late F	Refer	ence		 	 	 	 217
	7.28.1	Detailed I	Des	criptio	n.										 	 	 	 217
7.29	qpp::is_	_iterable<	< T , t	ypena	me >	> St	truct	Tem	plate	Ref	erend	е			 	 	 	 218
	7.29.1	Detailed I	Des	criptio	n .										 	 	 	 218
7.30		_iterable< d()), decIty																219
	7.30.1	Detailed I	Des	criptio	n	 220
7.31	qpp::is_	_matrix_ex	xpre	ssion<	< De	erive	ed >	Stru	ct Te	mpla	ite Re	eferei	псе		 	 	 	 220
	7.31.1	Detailed I	Des	criptio	n .										 	 	 	 220
7.32	qpp::Q	Circuit::iter	erato	r Class	s Ref	fere	nce								 	 	 	 221
	7.32.1	Detailed I	Des	criptio	n	 222
	7.32.2	Member ⁻	Туре	edef D	ocun	men	ıtatio	n							 	 	 	 222
		7.32.2.1	dif	ferenc	e_typ	pe .									 	 	 	 222
		7.32.2.2	ite	rator_c	categ	gory	<i>'</i>								 	 	 	 222
		7.32.2.3	ро	inter											 	 	 	 223

	7.32.2.4 reference
	7.32.2.5 value_type
7.32	3 Constructor & Destructor Documentation
	7.32.3.1 iterator() [1/2]
	7.32.3.2 iterator() [2/2]
7.32	Member Function Documentation
	7.32.4.1 operator"!=()
	7.32.4.2 operator*()
	7.32.4.3 operator++() [1/2]
	7.32.4.4 operator++() [2/2]
	7.32.4.5 operator=()
	7.32.4.6 operator==()
	7.32.4.7 set_begin_()
	7.32.4.8 set_end_()
7.32	5 Member Data Documentation
	7.32.5.1 elem
	7.32.5.2 qc
7.33 qpp	make_void < Ts > Struct Template Reference
7.33	Detailed Description
7.33	2 Member Typedef Documentation
	7.33.2.1 type
7.34 qpp	exception::MatrixMismatchSubsys Class Reference
7.34	Detailed Description
7.34	2 Member Function Documentation
	7.34.2.1 Exception()
	7.34.2.2 type_description()
7.35 qpp	exception::MatrixNotCvector Class Reference
7.35	Detailed Description
7.35	2 Member Function Documentation
	7.35.2.1 Exception()

CONTENTS xxi

		7.35.2.2 type_description()	231
7.36	qpp::ex	ception::MatrixNotRvector Class Reference	231
	7.36.1	Detailed Description	232
	7.36.2	Member Function Documentation	232
		7.36.2.1 Exception()	232
		7.36.2.2 type_description()	233
7.37	qpp::ex	ception::MatrixNotSquare Class Reference	233
	7.37.1	Detailed Description	234
	7.37.2	Member Function Documentation	234
		7.37.2.1 Exception()	234
		7.37.2.2 type_description()	235
7.38	qpp::ex	ception::MatrixNotSquareNorCvector Class Reference	235
	7.38.1	Detailed Description	236
	7.38.2	Member Function Documentation	236
		7.38.2.1 Exception()	236
		7.38.2.2 type_description()	237
7.39	qpp::ex	ception::MatrixNotSquareNorRvector Class Reference	237
	7.39.1	Detailed Description	238
	7.39.2	Member Function Documentation	238
		7.39.2.1 Exception()	238
		7.39.2.2 type_description()	239
7.40	qpp::ex	ception::MatrixNotSquareNorVector Class Reference	239
	7.40.1	Detailed Description	240
	7.40.2	Member Function Documentation	240
		7.40.2.1 Exception()	240
		7.40.2.2 type_description()	241
7.41	qpp::ex	ception::MatrixNotVector Class Reference	241
	7.41.1	Detailed Description	242
	7.41.2	Member Function Documentation	242
		7.41.2.1 Exception()	242

xxii CONTENTS

		7.41.2.2 type_description()
7.42	qpp::Q	Circuit::MeasureStep Struct Reference
	7.42.1	Detailed Description
	7.42.2	Constructor & Destructor Documentation
		7.42.2.1 MeasureStep() [1/2]
		7.42.2.2 MeasureStep() [2/2]
	7.42.3	Member Data Documentation
		7.42.3.1 c_reg
		7.42.3.2 mats_hash
		7.42.3.3 measurement_type
		7.42.3.4 name
		7.42.3.5 target
7.43	qpp::ex	cception::NoCodeword Class Reference
	7.43.1	Detailed Description
	7.43.2	Member Function Documentation
		7.43.2.1 Exception()
		7.43.2.2 type_description()
7.44	qpp::No	oiseBase < T > Class Template Reference
	7.44.1	Detailed Description
	7.44.2	Member Typedef Documentation
		7.44.2.1 noise_type
	7.44.3	Constructor & Destructor Documentation
		7.44.3.1 NoiseBase() [1/2]
		7.44.3.2 NoiseBase() [2/2]
		7.44.3.3 ~NoiseBase()
	7.44.4	Member Function Documentation
		7.44.4.1 compute_probs_()
		7.44.4.2 compute_state_()
		7.44.4.3 get_d()
		7.44.4.4 get_Ks()

CONTENTS xxiii

		7.44.4.5 get_last_idx()	52
		7.44.4.6 get_last_K()	52
		7.44.4.7 get_last_p()	53
		7.44.4.8 get_probs()	53
		7.44.4.9 operator()() [1/3]	53
		7.44.4.10 operator()() [2/3]	53
		7.44.4.11 operator()() [3/3]	54
	7.44.5	Member Data Documentation	54
		7.44.5.1 d	54
		7.44.5.2 generated	55
		7.44.5.3 i	55
		7.44.5.4 Ks	55
		7.44.5.5 probs	55
7.45	qpp::No	oiseType Class Reference	55
	7.45.1	Detailed Description	56
7.46	qpp::ex	cception::NotBipartite Class Reference	56
	7.46.1	Detailed Description	57
	7.46.2	Member Function Documentation	57
		7.46.2.1 Exception()	57
		7.46.2.2 type_description()	58
7.47	qpp::ex	cception::NotImplemented Class Reference	58
	7.47.1	Detailed Description	59
	7.47.2	Member Function Documentation	59
		7.47.2.1 Exception()	59
		7.47.2.2 type_description()	60
7.48	qpp::ex	cception::NotQubitCvector Class Reference	30
	7.48.1	Detailed Description	31
	7.48.2	Member Function Documentation	31
		7.48.2.1 Exception()	31
		7.48.2.2 type_description()	32

xxiv CONTENTS

7.49	qpp::ex	xception::NotQubitMatrix Class Reference	32
	7.49.1	Detailed Description	33
	7.49.2	Member Function Documentation	33
		7.49.2.1 Exception()	33
		7.49.2.2 type_description()	34
7.50	qpp::ex	xception::NotQubitRvector Class Reference	34
	7.50.1	Detailed Description	35
	7.50.2	Member Function Documentation	35
		7.50.2.1 Exception()	35
		7.50.2.2 type_description()	36
7.51	qpp::ex	xception::NotQubitSubsys Class Reference	36
	7.51.1	Detailed Description	37
	7.51.2	Member Function Documentation	37
		7.51.2.1 Exception()	37
		7.51.2.2 type_description()	38
7.52	qpp::ex	xception::NotQubitVector Class Reference	38
	7.52.1	Detailed Description	39
	7.52.2	Member Function Documentation	39
		7.52.2.1 Exception()	39
		7.52.2.2 type_description()	70
7.53	qpp::ex	xception::OutOfRange Class Reference	70
	7.53.1	Detailed Description	71
	7.53.2	Member Function Documentation	71
		7.53.2.1 Exception()	71
		7.53.2.2 type_description()	72
7.54	qpp::ex	xception::PermInvalid Class Reference	72
	7.54.1	Detailed Description	73
	7.54.2	Member Function Documentation	73
		7.54.2.1 Exception()	73
		7.54.2.2 type_description()	74

CONTENTS xxv

7.55	qpp::ex	cception::PermMismatchDims Class Reference
	7.55.1	Detailed Description
	7.55.2	Member Function Documentation
		7.55.2.1 Exception()
		7.55.2.2 type_description()
7.56	qpp::Q	Circuit Class Reference
	7.56.1	Detailed Description
	7.56.2	Member Typedef Documentation
		7.56.2.1 const_iterator
	7.56.3	Member Enumeration Documentation
		7.56.3.1 GateType
		7.56.3.2 MeasureType
		7.56.3.3 StepType
	7.56.4	Constructor & Destructor Documentation
		7.56.4.1 QCircuit()
		7.56.4.2 ~QCircuit()
	7.56.5	Member Function Documentation
		7.56.5.1 add_hash_()
		7.56.5.2 begin() [1/2]
		7.56.5.3 begin() [2/2]
		7.56.5.4 cbegin()
		7.56.5.5 cCTRL() [1/4]
		7.56.5.6 cCTRL() [2/4]
		7.56.5.7 cCTRL() [3/4]
		7.56.5.8 cCTRL() [4/4]
		7.56.5.9 cCTRL_custom()
		7.56.5.10 cend()
		7.56.5.11 CTRL() [1/4]
		7.56.5.12 CTRL() [2/4]
		7.56.5.13 CTRL() [3/4]

xxvi CONTENTS

7.56.5.14 CTRL() [4/4]
7.56.5.15 CTRL_custom()
7.56.5.16 display()
7.56.5.17 end() [1/2]
7.56.5.18 end() [2/2]
7.56.5.19 gate() [1/3]
7.56.5.20 gate() [2/3]
7.56.5.21 gate() [3/3]
7.56.5.22 gate_custom()
7.56.5.23 gate_fan() [1/3]
7.56.5.24 gate_fan() [2/3]
7.56.5.25 gate_fan() [3/3]
7.56.5.26 get_cmat_hash_tbl_()
7.56.5.27 get_d()
7.56.5.28 get_gate_count()
7.56.5.29 get_gate_depth()
7.56.5.30 get_gates_()
7.56.5.31 get_measured() [1/2]
7.56.5.32 get_measured() [2/2]
7.56.5.33 get_measurement_count() [1/2]
7.56.5.34 get_measurement_count() [2/2]
7.56.5.35 get_measurements_()
7.56.5.36 get_name()
7.56.5.37 get_nc()
7.56.5.38 get_non_measured()
7.56.5.39 get_nop_count()
7.56.5.40 get_nq()
7.56.5.41 get_step_count()
7.56.5.42 measureV() [1/2]
7.56.5.43 measureV() [2/2]

CONTENTS xxvii

		7.56.5.44 measureZ()	298
		7.56.5.45 nop()	299
		7.56.5.46 QFT() [1/3]	299
		7.56.5.47 QFT() [2/3]	299
		7.56.5.48 QFT() [3/3]	300
		7.56.5.49 TFQ() [1/3]	300
		7.56.5.50 TFQ() [2/3]	301
		7.56.5.51 TFQ() [3/3]	301
		7.56.5.52 to_JSON()	301
	7.56.6	Friends And Related Function Documentation	302
		7.56.6.1 operator << [1/4]	302
		7.56.6.2 operator << [2/4]	302
		7.56.6.3 operator << [3/4]	303
		7.56.6.4 operator << [4/4]	303
		7.56.6.5 QEngine	303
	7.56.7	Member Data Documentation	303
		7.56.7.1 cmat_hash_tbl	304
		7.56.7.2 count	304
		7.56.7.3 d	304
		7.56.7.4 gates	304
		7.56.7.5 measured	304
		7.56.7.6 measurement_count	304
		7.56.7.7 measurements	305
		7.56.7.8 name	305
		7.56.7.9 nc	305
		7.56.7.10 nq	305
		7.56.7.11 step_types	305
7.57	qpp::Ql	Engine Class Reference	306
	7.57.1	Detailed Description	308
	7.57.2	Constructor & Destructor Documentation	308

xxviii CONTENTS

	7.57.2.1 QEngine() [1/3])8
	7.57.2.2 QEngine() [2/3])8
	7.57.2.3 QEngine() [3/3])9
	7.57.2.4 ~QEngine())9
7.57.3	Member Function Documentation)9
	7.57.3.1 display())9
	7.57.3.2 execute() [1/2])9
	7.57.3.3 execute() [2/2]	10
	7.57.3.4 get_circuit()	10
	7.57.3.5 get_dit()	10
	7.57.3.6 get_dits()	11
	7.57.3.7 get_measured() [1/2]	11
	7.57.3.8 get_measured() [2/2]	11
	7.57.3.9 get_non_measured()	12
	7.57.3.10 get_probs()	12
	7.57.3.11 get_psi()	12
	7.57.3.12 get_relative_pos_()	12
	7.57.3.13 operator=()	13
	7.57.3.14 reset()	13
	7.57.3.15 set_dit()	13
	7.57.3.16 set_measured_()	14
	7.57.3.17 set_psi()	14
	7.57.3.18 to_JSON()	14
7.57.4	Member Data Documentation	15
	7.57.4.1 dits	15
	7.57.4.2 probs	15
	7.57.4.3 psi	15
	7.57.4.4 qc	15
	7.57.4.5 subsys	16
7.58 qpp::0	NoisyEngine < NoiseModel > Class Template Reference	16

CONTENTS xxix

	7.58.1	Detailed Description	317
	7.58.2	Constructor & Destructor Documentation	317
		7.58.2.1 QNoisyEngine()	317
	7.58.3	Member Function Documentation	318
		7.58.3.1 execute() [1/2]	318
		7.58.3.2 execute() [2/2]	318
		7.58.3.3 get_noise_results()	319
	7.58.4	Member Data Documentation	319
		7.58.4.1 noise	319
		7.58.4.2 noise_results	319
7.59	qpp::Q	ubitAmplitudeDampingNoise Class Reference	320
	7.59.1	Detailed Description	321
	7.59.2	Constructor & Destructor Documentation	321
		7.59.2.1 QubitAmplitudeDampingNoise()	321
7.60	qpp::Q	ubitBitFlipNoise Class Reference	321
	7.60.1	Detailed Description	322
	7.60.2	Constructor & Destructor Documentation	322
		7.60.2.1 QubitBitFlipNoise()	322
7.61	qpp::Qı	ubitBitPhaseFlipNoise Class Reference	323
	7.61.1	Detailed Description	324
	7.61.2	Constructor & Destructor Documentation	324
		7.61.2.1 QubitBitPhaseFlipNoise()	324
7.62	qpp::Qı	ubitDepolarizingNoise Class Reference	324
	7.62.1	Detailed Description	325
	7.62.2	Constructor & Destructor Documentation	325
		7.62.2.1 QubitDepolarizingNoise()	325
7.63	qpp::Q	ubitPhaseDampingNoise Class Reference	326
	7.63.1	Detailed Description	327
	7.63.2	Constructor & Destructor Documentation	327
		7.63.2.1 QubitPhaseDampingNoise()	327

7.64	qpp::Qı	ubitPhaseFlipNoise Class Reference
	7.64.1	Detailed Description
	7.64.2	Constructor & Destructor Documentation
		7.64.2.1 QubitPhaseFlipNoise()
7.65	qpp::ex	cception::QuditAlreadyMeasured Class Reference
	7.65.1	Detailed Description
	7.65.2	Member Function Documentation
		7.65.2.1 Exception()
		7.65.2.2 type_description()
7.66	qpp::Qı	uditDepolarizingNoise Class Reference
	7.66.1	Detailed Description
	7.66.2	Constructor & Destructor Documentation
		7.66.2.1 QuditDepolarizingNoise()
	7.66.3	Member Function Documentation
		7.66.3.1 fill_Ks_()
		7.66.3.2 fill_probs_()
7.67	qpp::Ra	andomDevices Class Reference
	7.67.1	Detailed Description
	7.67.2	Constructor & Destructor Documentation
		7.67.2.1 RandomDevices()
		7.67.2.2 ~RandomDevices()
	7.67.3	Member Function Documentation
		7.67.3.1 get_prng()
		7.67.3.2 load()
		7.67.3.3 save()
	7.67.4	Friends And Related Function Documentation
		7.67.4.1 internal::Singleton < RandomDevices >
	7.67.5	Member Data Documentation
		7.67.5.1 prng
		7.67.5.2 rd

CONTENTS xxxi

7.68	qpp::int	rernal::Singleton< T > Class Template Reference
	7.68.1	Detailed Description
	7.68.2	Constructor & Destructor Documentation
		7.68.2.1 Singleton() [1/2]
		7.68.2.2 Singleton() [2/2]
		7.68.2.3 ~Singleton()
	7.68.3	Member Function Documentation
		7.68.3.1 get_instance()
		7.68.3.2 get_thread_local_instance()
		7.68.3.3 operator=()
7.69	qpp::ex	ception::SizeMismatch Class Reference
	7.69.1	Detailed Description
	7.69.2	Member Function Documentation
		7.69.2.1 Exception()
		7.69.2.2 type_description()
7.70	qpp::No	oiseType::StateDependent Class Reference
	7.70.1	Detailed Description
7.71	qpp::No	oiseType::StateIndependent Class Reference
	7.71.1	Detailed Description
7.72	qpp::St	ates Class Reference
	7.72.1	Detailed Description
	7.72.2	Constructor & Destructor Documentation
		7.72.2.1 States()
		7.72.2.2 ~States()
	7.72.3	Member Function Documentation
		7.72.3.1 jn()
		7.72.3.2 mes()
		7.72.3.3 minus()
		7.72.3.4 one()
		7.72.3.5 plus()

xxxii CONTENTS

		7.72.3.6 zero()	347
	7.72.4	Friends And Related Function Documentation	347
		7.72.4.1 internal::Singleton < const States >	347
	7.72.5	Member Data Documentation	347
		7.72.5.1 b00	348
		7.72.5.2 b01	348
		7.72.5.3 b10	348
		7.72.5.4 b11	348
		7.72.5.5 GHZ	348
		7.72.5.6 pb00	348
		7.72.5.7 pb01	349
		7.72.5.8 pb10	349
		7.72.5.9 pb11	349
		7.72.5.10 pGHZ	349
		7.72.5.11 pW	349
		7.72.5.12 px0	349
		7.72.5.13 px1	350
		7.72.5.14 py0	350
		7.72.5.15 py1	350
		7.72.5.16 pz0	350
		7.72.5.17 pz1	350
		7.72.5.18 W	350
		7.72.5.19 x0	351
		7.72.5.20 x1	351
		7.72.5.21 y0	351
		7.72.5.22 y1	351
		7.72.5.23 z0	351
		7.72.5.24 z1	351
7.73	qpp::ex	cception::SubsysMismatchDims Class Reference	352
	7.73.1	Detailed Description	353

CONTENTS xxxiii

	7.73.2	Member Function Documentation	53
		7.73.2.1 Exception()	53
		7.73.2.2 type_description()	53
7.74	qpp::Ti	mer < T, CLOCK_T > Class Template Reference	54
	7.74.1	Detailed Description	55
	7.74.2	Constructor & Destructor Documentation	55
		7.74.2.1 Timer() [1/3]	55
		7.74.2.2 Timer() [2/3]	56
		7.74.2.3 Timer() [3/3]	56
		7.74.2.4 ~Timer()	56
	7.74.3	Member Function Documentation	56
		7.74.3.1 display()	56
		7.74.3.2 get_duration()	57
		7.74.3.3 operator=() [1/2]	57
		7.74.3.4 operator=() [2/2]	57
		7.74.3.5 tic()	58
		7.74.3.6 tics()	58
		7.74.3.7 toc()	58
	7.74.4	Member Data Documentation	58
		7.74.4.1 end	58
		7.74.4.2 start	59
7.75	qpp::ex	cception::TypeMismatch Class Reference	59
	7.75.1	Detailed Description	60
	7.75.2	Member Function Documentation	60
		7.75.2.1 Exception()	60
		7.75.2.2 type_description()	61
7.76	qpp::ex	cception::UndefinedType Class Reference	61
	7.76.1	Detailed Description	62
	7.76.2	Member Function Documentation	62
		7.76.2.1 Exception()	62

	7.76.2.2 type_description()	363
7.77 qpp::	exception::Unknown Class Reference	363
7.77.	1 Detailed Description	364
7.77.	2 Member Function Documentation	364
	7.77.2.1 Exception()	364
	7.77.2.2 type_description()	365
7.78 qpp::	QCircuit::iterator::value_type_ Class Reference	365
7.78.	1 Detailed Description	366
7.78.	2 Constructor & Destructor Documentation	366
	7.78.2.1 value_type_() [1/2]	366
	7.78.2.2 value_type_() [2/2]	367
7.78.	3 Member Function Documentation	367
	7.78.3.1 display()	367
	7.78.3.2 operator=()	367
7.78.	4 Member Data Documentation	367
	7.78.4.1 gates_ip	368
	7.78.4.2 ip	368
	7.78.4.3 measurements_ip	368
	7.78.4.4 type	368
	7.78.4.5 value_type_qc	368
7.79 qpp::	exception::ZeroSize Class Reference	369
7.79.	1 Detailed Description	370
7.79.	2 Member Function Documentation	370
	7.79.2.1 Exception()	370
	7.79.2.2 type_description()	370

CONTENTS XXXV

8	File I	Documentation	371
	8.1	classes/circuits/circuits.h File Reference	371
		8.1.1 Detailed Description	372
	8.2	classes/circuits/engines.h File Reference	372
		8.2.1 Detailed Description	372
	8.3	classes/codes.h File Reference	373
		8.3.1 Detailed Description	373
	8.4	classes/exception.h File Reference	373
		8.4.1 Detailed Description	375
	8.5	classes/gates.h File Reference	375
		8.5.1 Detailed Description	376
	8.6	classes/idisplay.h File Reference	376
		8.6.1 Detailed Description	377
	8.7	classes/init.h File Reference	377
		8.7.1 Detailed Description	377
	8.8	classes/noise.h File Reference	378
		8.8.1 Detailed Description	378
	8.9	classes/random_devices.h File Reference	379
		8.9.1 Detailed Description	379
	8.10	classes/reversible.h File Reference	379
		8.10.1 Detailed Description	380
	8.11	classes/states.h File Reference	380
		8.11.1 Detailed Description	381
	8.12	classes/timer.h File Reference	381
		8.12.1 Detailed Description	381
	8.13	constants.h File Reference	382
		8.13.1 Detailed Description	383
	8.14	entanglement.h File Reference	383
		8.14.1 Detailed Description	384
	8.15	entropies.h File Reference	384

xxxvi CONTENTS

Index		409
8.31	/Users/vlad/qpp/README.md File Reference	408
0.04	8.30.1 Detailed Description	
8.30	types.h File Reference	
0.00	8.29.1 Detailed Description	
8.29	traits.h File Reference	
0.00	8.28.1 Detailed Description	
8.28	statistics.h File Reference	
0.05	8.27.1 Detailed Description	
8.27	random.h File Reference	
	8.26.2.1 QPP_UNUSED	
	8.26.2 Macro Definition Documentation	
	8.26.1 Detailed Description	
8.26	qpp.h File Reference	
_	8.25.1 Detailed Description	
8.25	operations.h File Reference	
_	8.24.1 Detailed Description	
8.24	number_theory.h File Reference	
	8.23.1 Detailed Description	
8.23	MATLAB/matlab.h File Reference	
	8.22.1 Detailed Description	
8.22	internal/util.h File Reference	
	8.21.1 Detailed Description	
8.21	internal/classes/singleton.h File Reference	
	8.20.1 Detailed Description	
8.20	internal/classes/iomanip.h File Reference	393
	8.19.1 Detailed Description	
8.19	instruments.h File Reference	392
	8.18.1 Detailed Description	392
8.18	input_output.h File Reference	391
	8.17.1 Detailed Description	391
8.17	functions.h File Reference	386
	8.16.1 Detailed Description	386
8.16	experimental/experimental.h File Reference	386
	8.15.1 Detailed Description	385

Chapter 1

Quantum++

Version 1.2 - 10 February 2019

Build status:

Chat (questions/issues)

About

Quantum++ is a modern C++11 general purpose quantum computing library, composed solely of template header files. Quantum++ is written in standard C++11 and has very low external dependencies, using only the Eigen 3 linear algebra header-only template library and, if available, the OpenMP multi-processing library.

Quantum++ is not restricted to qubit systems or specific quantum information processing tasks, being capable of simulating arbitrary quantum processes. The main design factors taken in consideration were the ease of use, high portability, and high performance. The library's simulation capabilities are only restricted by the amount of available physical memory. On a typical machine (Intel i5 8Gb RAM) Quantum++ can successfully simulate the evolution of 25 qubits in a pure state or of 12 qubits in a mixed state reasonably fast.

To report any bugs or ask for additional features/enhancements, please submit an issue with an appropriate label.

If you are interesting in contributing to this project, feel free to contact me. Alternatively, create a custom branch, add your contribution, then finally create a pull request. If I accept the pull request, I will merge your custom branch with the latest development branch. The latter will eventually be merged into a future release version. To contribute, you need to have a solid knowledge of C++ (preferably C++11), including templates and the standard library, a basic knowledge of quantum computing and linear algebra, and working experience with Eigen 3.

For additional Eigen 3 documentation see http://eigen.tuxfamily.org/dox/. For a simple Eigen 3 quick ASCII reference see http://eigen.tuxfamily.org/dox/AsciiQuickReference.txt.

Copyright (c) 2013 - 2019 Vlad Gheorghiu, vgheorgh AT gmail DOT com.

License

Quantum++ is distributed under the MIT license. Please see the LICENSE file for more details.

Installation instructions and further documentation

Please see the installation guide https://github.com/vsoftco/qpp/blob/master/INSTALL.md "`INSTALL.md`" and the comprehensive Wiki for further documentation and detailed examples.

The official API documentation is available in PDF and HTML formats in the doc folder.

2 Quantum++

Chapter 2

Namespace Index

2.1 Namespace List

Here is a list of all namespaces with brief descriptions:

qpp
Quantum++ main namespace
qpp::exception
Quantum++ exception hierarchy namespace
qpp::experimental
Experimental/test functions/classes, do not use or modify
qpp::internal
Internal utility functions, do not use them directly or modify them
qpp::literals

4 Namespace Index

Chapter 3

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

qpp::internal::Display_Impl
qpp::internal::IOManipEigen
qpp::internal::EqualEigen
std::exception
qpp::exception::Exception
qpp::exception::CustomException
qpp::exception::DimsInvalid
qpp::exception::DimsMismatchCvector
qpp::exception::DimsMismatchMatrix
qpp::exception::DimsMismatchRvector
qpp::exception::DimsMismatchVector
qpp::exception::DimsNotEqual
qpp::exception::Duplicates
qpp::exception::InvalidIterator
qpp::exception::MatrixMismatchSubsys
qpp::exception::MatrixNotCvector
qpp::exception::MatrixNotRvector
qpp::exception::MatrixNotSquare
qpp::exception::MatrixNotSquareNorCvector
qpp::exception::MatrixNotSquareNorRvector
qpp::exception::MatrixNotSquareNorVector
qpp::exception::MatrixNotVector
qpp::exception::NoCodeword
qpp::exception::NotBipartite
qpp::exception::NotImplemented
qpp::exception::NotQubitCvector
qpp::exception::NotQubitMatrix
qpp::exception::NotQubitRvector
qpp::exception::NotQubitSubsys
qpp::exception::NotQubitVector
qpp::exception::OutOfRange
qpp::exception::PermInvalid
qpp::exception::PermMismatchDims
qpp::exception::QuditAlreadyMeasured
app::exception::SizeMismatch

6 Hierarchical Index

qpp::exception::SubsysMismatchDims
qpp::exception::TypeMismatch
qpp::exception::UndefinedType
qpp::exception::Unknown
qpp::exception::ZeroSize
false_type
qpp::is_complex < T >
qpp::is_iterable < T, typename >
qpp::Bit_circuit::Gate_count
qpp::Bit_circuit::Gate_depth175qpp::QCircuit::GateStep194
qpp::internal::HashEigen
qpp::IDisplay
qpp::Dynamic bitset
qpp::Bit circuit
qpp::internal::IOManipEigen
qpp::internal::IOManipPointer< PointerType >
qpp::internal::IOManipRange< InputIterator >
qpp::QCircuit
qpp::QCircuit::iterator::value_type
qpp::QEngine
qpp::QNoisyEngine < NoiseModel >
qpp::Timer< T, CLOCK_T >
qpp::IJSON
qpp::QCircuit
qpp::QEngine
is base of
app::is_matrix_expression< Derived >
qpp::QCircuit::iterator
qpp::make void < Ts >
qpp::QCircuit::MeasureStep
qpp::NoiseBase< T >
qpp::NoiseBase < NoiseType::StateDependent >
qpp::QubitAmplitudeDampingNoise
qpp::QubitPhaseDampingNoise
qpp::NoiseBase< NoiseType::StateIndependent >
qpp::QubitBitFlipNoise
qpp::QubitBitPhaseFlipNoise
qpp::QubitDepolarizingNoise
qpp::QubitPhaseFlipNoise
qpp::QuditDepolarizingNoise
qpp::NoiseType
qpp::internal::Singleton< T >
$qpp::internal::Singleton < const \ Codes > \dots $
qpp::Codes
qpp::internal::Singleton < const Gates >
qpp::Gates
app::internal::Singleton < const Init >
qpp::Init
qpp::internal::Singleton < const States >
qpp::States
qpp::internal::Singleton< RandomDevices >
qpp::RandomDevices
qpp::NoiseType::StateDependent
qpp::NoiseType::StateIndependent

3.1 Class Hierarchy 7

true_type	
$qpp::is_complex < std::complex < T >> \ \ldots \ \ldots$	217
qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval<	T
>().end()), decltype(*(std::declyal< T >().begin()))> >	219

8 Hierarchical Index

Chapter 4

Class Index

4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

qpp::Bit_circuit
Classical reversible circuit simulator
qpp::Codes
Const Singleton class that defines quantum error correcting codes
qpp::exception::CustomException
Custom exception
qpp::exception::DimsInvalid
Invalid dimension(s) exception
qpp::exception::DimsMismatchCvector
Dimension(s) mismatch column vector size exception
qpp::exception::DimsMismatchMatrix
Dimension(s) mismatch matrix size exception
qpp::exception::DimsMismatchRvector
Dimension(s) mismatch row vector size exception
qpp::exception::DimsMismatchVector
Dimension(s) mismatch vector size exception
qpp::exception::DimsNotEqual
Dimensions not equal exception
qpp::internal::Display_Impl
qpp::exception::Duplicates
System (e.g. std::vector) has duplicates exception
qpp::Dynamic_bitset
Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std←
::bitset <n>)</n>
qpp::internal::EqualEigen
Functor for comparing Eigen expressions for equality
qpp::exception::Exception
Base class for generating Quantum++ custom exceptions
qpp::Bit_circuit::Gate_count
Gate counters
qpp::Bit_circuit::Gate_depth
Gate depth
qpp::Gates
Const Singleton class that implements most commonly used gates
qpp::QCircuit::GateStep
One step consisting only of gates/operators in the circuit

10 Class Index

qpp::internal::HashEigen	
Functor for hashing Eigen expressions	197
qpp::IDisplay	
Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream&	& os) const
198	
qpp::IJSON	
Abstract class (interface) that mandates the definition of very basic JSON serialization support	201
qpp::Init	
Const Singleton class that performs additional initializations/cleanups	203
gpp::exception::InvalidIterator	
Invalid iterator	205
qpp::internal::IOManipEigen	
<pre>qpp::internal::IOManipPointer< PointerType ></pre>	
qpp::internal::IOManipRange < InputIterator >	
	213
qpp::is_complex < T >	016
Checks whether the type is a complex type	210
qpp::is_complex < std::complex < T > >	047
Checks whether the type is a complex number type, specialization for complex types	217
qpp::is_iterable < T, typename >	0.10
Checks whether T is compatible with an STL-like iterable container	
qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval< T >().end()), decltype(std::de	ecItype(*(std::decIval<
Checks whether T is compatible with an STL-like iterable container, specialization for STL-like	
iterable containers	219
qpp::is_matrix_expression< Derived >	
Checks whether the type is an Eigen matrix expression	220
qpp::QCircuit::iterator	
Quantum circuit bound-checking (safe) iterator	221
qpp::make_void < Ts >	
Helper for qpp::to_void<> alias template	226
qpp::exception::MatrixMismatchSubsys	
Matrix mismatch subsystems exception	227
qpp::exception::MatrixNotCvector	
Matrix is not a column vector exception	229
qpp::exception::MatrixNotRvector	
Matrix is not a row vector exception	231
qpp::exception::MatrixNotSquare	
Matrix is not square exception	233
qpp::exception::MatrixNotSquareNorCvector	
Matrix is not square nor column vector exception	235
qpp::exception::MatrixNotSquareNorRvector	
Matrix is not square nor row vector exception	237
pp::exception::MatrixNotSquareNorVector	207
Matrix is not square nor vector exception	230
pp::exception::MatrixNotVector	200
Matrix is not a vector exception	2/11
·	241
qpp::QCircuit::MeasureStep One step consisting only of measurements in the circuit	040
· · · · · · · · · · · · · · · · · · ·	243
qpp::exception::NoCodeword	0.40
Codeword does not exist exception	246
qpp::NoiseBase< T >	0.40
Base class for all noise models, derive your particular noise model	248
qpp::NoiseType	0.55
Contains template tags used to specify the noise type	255
qpp::exception::NotBipartite	
Not bi-partite exception	256
qpp::exception::NotImplemented	
Code not yet implemented	258

4.1 Class List

qpp::exception::NotQubitCvector	
Column vector is not 2 x 1 exception	260
qpp::exception::NotQubitMatrix	
Matrix is not 2 x 2 exception	262
qpp::exception::NotQubitRvector	
Row vector is not 1 x 2 exception	264
qpp::exception::NotQubitSubsys	
Subsystems are not qubits exception	266
qpp::exception::NotQubitVector	
Vector is not 2 x 1 nor 1 x 2 exception	268
qpp::exception::OutOfRange	
Argument out of range exception	270
qpp::exception::PermInvalid	
Invalid permutation exception	272
qpp::exception::PermMismatchDims	
Permutation mismatch dimensions exception	274
qpp::QCircuit	
Quantum circuit class	276
qpp::QEngine	000
Quantum circuit engine, executes qpp::QCircuit	306
qpp::QNoisyEngine < NoiseModel >	040
Noisy quantum circuit engine, executes qpp::QCircuit	316
qpp::QubitAmplitudeDampingNoise	320
Qubit amplitude damping noise, as described in Nielsen and Chuang	320
Qubit bit flip noise	321
qpp::QubitBitPhaseFlipNoise	321
Qubit bit-phase flip (dephasing) noise	323
qpp::QubitDepolarizingNoise	020
Qubit depolarizing noise	324
qpp::QubitPhaseDampingNoise	0
Qubit phase damping noise, as described in Nielsen and Chuang	326
qpp::QubitPhaseFlipNoise	
Qubit phase flip (dephasing) noise	327
qpp::exception::QuditAlreadyMeasured	
Qudit was already measured exception	329
qpp::QuditDepolarizingNoise	
Qudit depolarizing noise	331
qpp::RandomDevices	
Singleton class that manages the source of randomness in the library	334
qpp::internal::Singleton< T >	
Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously	
recurring template pattern)	337
qpp::exception::SizeMismatch	
Size mismatch exception	340
qpp::NoiseType::StateDependent	
Template tag, used whenever the noise is state-dependent	342
qpp::NoiseType::StateIndependent	- 4-
Template tag, used whenever the noise is state-independent	342
qpp::States	0.40
Const Singleton class that implements most commonly used states	342
qpp::exception::SubsysMismatchDims Subsystems mismatch dimensions exception	352
qpp::Timer < T, CLOCK_T >	002
Chronometer	354
qpp::exception::TypeMismatch	004
Type mismatch exception	359
M	

12 Class Index

qpp::exception::UndefinedType	
Not defined for this type exception	361
qpp::exception::Unknown	
Unknown exception	363
qpp::QCircuit::iterator::value_type_	
Value type class for qpp::QCircuit::iterator	365
qpp::exception::ZeroSize	
Object has zero size exception	369

Chapter 5

File Index

5.1 File List

Here is a list of all files with brief descriptions:

constants.h	
Constants	882
entanglement.h	
Entanglement functions	883
entropies.h	
17	384
functions.h	
	386
input_output.h	
' '	391
instruments.h	
	392
number_theory.h	
,	397
operations.h	
•	399
qpp.h	
· · · · · · · · · · · · · · · · · · ·	101
random.h	
	103
statistics.h	
	105
traits.h	
,,	106
types.h	
)	107
classes/codes.h	. 7.
· · · · · · · · · · · · · · · · · · ·	373
classes/exception.h	70
·	373
classes/gates.h	75
	375
classes/idisplay.h	
Display interface via the non-virtual interface (NVI) and very basic JSON serialization support	7,
interface	376

14 File Index

classes/init.h	
Initialization	377
classes/noise.h	
Noise models	378
classes/random_devices.h	
Random devices	379
classes/reversible.h	
Support for classical reversible circuits	379
classes/states.h	
Quantum states	380
classes/timer.h	
Timing	381
classes/circuits/circuits.h	
Qudit quantum circuits	371
classes/circuits/engines.h	
Qudit quantum engines	372
experimental/experimental.h	
Experimental/test functions/classes	386
nternal/util.h	
Internal utility functions	395
internal/classes/iomanip.h	
Input/output manipulators	393
nternal/classes/singleton.h	
Singleton pattern via CRTP	394
MATLAB/matlab.h	
Input/output interfacing with MATLAB	397

Chapter 6

Namespace Documentation

6.1 qpp Namespace Reference

Quantum++ main namespace.

Namespaces

· exception

Quantum++ exception hierarchy namespace.

· experimental

Experimental/test functions/classes, do not use or modify.

internal

Internal utility functions, do not use them directly or modify them.

literals

Classes

· class Bit_circuit

Classical reversible circuit simulator.

• class Codes

const Singleton class that defines quantum error correcting codes

· class Dynamic_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

· class Gates

const Singleton class that implements most commonly used gates

class IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

class IJSON

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

class Init

const Singleton class that performs additional initializations/cleanups

· struct is complex

Checks whether the type is a complex type.

• struct is_complex< std::complex< T > >

Checks whether the type is a complex number type, specialization for complex types.

· struct is_iterable

Checks whether T is compatible with an STL-like iterable container.

 $\bullet \ \ struct\ is_iterable < T,\ to_void < \ decltype(std::declval < T>().begin()),\ decltype(std::declval < T>().end()),\ decltype(*(std::declval < T>().end())),\ decltype(*(std::declval < T>().end()$

Checks whether T is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

• struct is_matrix_expression

Checks whether the type is an Eigen matrix expression.

· struct make void

Helper for qpp::to_void<> alias template.

· class NoiseBase

Base class for all noise models, derive your particular noise model.

class NoiseType

Contains template tags used to specify the noise type.

class QCircuit

Quantum circuit class.

· class QEngine

Quantum circuit engine, executes qpp::QCircuit.

class QNoisyEngine

Noisy quantum circuit engine, executes qpp::QCircuit.

· class QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

• class QubitBitFlipNoise

Qubit bit flip noise.

· class QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

· class QubitDepolarizingNoise

Qubit depolarizing noise.

• class QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

· class QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

· class QuditDepolarizingNoise

Qudit depolarizing noise.

· class RandomDevices

Singleton class that manages the source of randomness in the library.

· class States

const Singleton class that implements most commonly used states

class Timer

Chronometer.

Typedefs

```
    template<typename... Ts>
    using to void = typename make void< Ts... >::type
```

Alias template that implements the proposal for void_t.

using idx = std::size_t

Non-negative integer index, make sure you use an unsigned type.

• using bigint = long long int

Big integer.

• using cplx = std::complex< double >

Complex number in double precision.

• using ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector.

• using bra = Eigen::RowVectorXcd

Complex (double precision) dynamic Eigen row vector.

using cmat = Eigen::MatrixXcd

Complex (double precision) dynamic Eigen matrix.

using dmat = Eigen::MatrixXd

Real (double precision) dynamic Eigen matrix.

template<typename Scalar >

```
using dyn_mat = Eigen::Matrix < Scalar, Eigen::Dynamic, Eigen::Dynamic >
```

Dynamic Eigen matrix over the field specified by Scalar.

template<typename Scalar >

```
using dyn_col_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 >
```

Dynamic Eigen column vector over the field specified by Scalar.

template<typename Scalar >

```
using dyn_row_vect = Eigen::Matrix < Scalar, 1, Eigen::Dynamic >
```

Dynamic Eigen row vector over the field specified by Scalar.

Functions

constexpr cplx operator" i (long double x) noexcept

User-defined literal for complex $i = \sqrt{-1}$ (real overload)

cplx omega (idx D)

D-th root of unity.

template<typename Derived >

dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx >
&dims)

Schmidt coefficients of the bi-partite pure state A.

• template<typename Derived >

```
dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2)
```

Schmidt coefficients of the bi-partite pure state A.

• template<typename Derived >

```
cmat schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
```

Schmidt basis on Alice side.

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

```
cmat schmidtA (const Eigen::MatrixBase< Derived > &A, idx d=2)
```

Schmidt basis on Alice side.

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

```
cmat schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
```

Schmidt basis on Bob side.

template<typename Derived >

```
cmat schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2)
```

Schmidt basis on Bob side.

template<typename Derived >

std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)

Schmidt probabilities of the bi-partite pure state A.

• template<typename Derived >

```
std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)
```

Schmidt probabilities of the bi-partite pure state A.

```
• template<typename Derived >
  double entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Entanglement of the bi-partite pure state A.
template<typename Derived >
  double entanglement (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Entanglement of the bi-partite pure state A.
template<typename Derived >
  double gconcurrence (const Eigen::MatrixBase< Derived > &A)
     G-concurrence of the bi-partite pure state A.
• template<typename Derived >
  double negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Negativity of the bi-partite mixed state A.

    template<typename Derived >

  double negativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Logarithmic negativity of the bi-partite mixed state A.
• template<typename Derived >
  double lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Logarithmic negativity of the bi-partite mixed state A.
• template<typename Derived >
  double concurrence (const Eigen::MatrixBase< Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.

    template<typename Derived >

  double entropy (const Eigen::MatrixBase< Derived > &A)
      von-Neumann entropy of the density matrix A

    double entropy (const std::vector< double > &prob)

     Shannon entropy of the probability distribution prob.

    template<typename Derived >

  double renyi (const Eigen::MatrixBase< Derived > &A, double alpha)
      Renyi-\alpha entropy of the density matrix A, for \alpha > 0.

    double renyi (const std::vector< double > &prob, double alpha)

     Renyi- \alpha entropy of the probability distribution prob, for \alpha > 0.
• template<typename Derived >
  double tsallis (const Eigen::MatrixBase< Derived > &A, double q)
      Tsallis- q entropy of the density matrix A, for q > 0.

    double tsallis (const std::vector< double > &prob, double q)

      Tsallis- q entropy of the probability distribution prob, for q \geq 0.
• template<typename Derived >
  double gmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx > \&subsysB, const std::vector<math>< idx > \&dims)
      Quantum mutual information between 2 subsystems of a composite system.

    template<typename Derived >

  double qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx > &subsysB, idx d=2)
      Quantum mutual information between 2 subsystems of a composite system.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > transpose (const Eigen::MatrixBase< Derived > &A)
      Transpose.
template<typename Derived >
  dyn mat< typename Derived::Scalar > conjugate (const Eigen::MatrixBase< Derived > &A)
     Complex conjugate.
```

```
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > adjoint (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > inverse (const Eigen::MatrixBase< Derived > &A)
     Inverse.

    template<typename Derived >

  Derived::Scalar trace (const Eigen::MatrixBase< Derived > &A)
     Trace.

    template<typename Derived >

  Derived::Scalar det (const Eigen::MatrixBase< Derived > &A)
     Determinant.

    template<typename Derived >

  Derived::Scalar logdet (const Eigen::MatrixBase< Derived > &A)
     Logarithm of the determinant.
• template<typename Derived >
  Derived::Scalar sum (const Eigen::MatrixBase< Derived > &A)
     Element-wise sum of A.

    template<typename Derived >

  Derived::Scalar prod (const Eigen::MatrixBase< Derived > &A)
     Element-wise product of A.

    template<typename Derived >

  double norm (const Eigen::MatrixBase< Derived > &A)
     Frobenius norm.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > normalize (const Eigen::MatrixBase< Derived > &A)
     Normalizes state vector (column or row vector) or density matrix.

    template<typename Derived >

  std::pair< dyn col vect< cplx >, cmat > eig (const Eigen::MatrixBase< Derived > &A)
     Full eigen decomposition.

    template<typename Derived >

  dyn_col_vect< cplx > evals (const Eigen::MatrixBase< Derived > &A)
     Eigenvalues.

    template<typename Derived >

  cmat evects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors.

    template<typename Derived >

  std::pair< dyn_col_vect< double >, cmat > heig (const Eigen::MatrixBase< Derived > &A)
     Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > hevals (const Eigen::MatrixBase< Derived > &A)
     Hermitian eigenvalues.
• template<typename Derived >
  cmat hevects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors of Hermitian matrix.

    template<typename Derived >

  std::tuple< cmat, dyn_col_vect< double >, cmat > svd (const Eigen::MatrixBase< Derived > &A)
     Full singular value decomposition.
• template<typename Derived >
  dyn_col_vect< double > svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.

    template<typename Derived >

  cmat svdU (const Eigen::MatrixBase< Derived > &A)
```

Kronecker power.

```
Left singular vectors.
• template<typename Derived >
  cmat svdV (const Eigen::MatrixBase< Derived > &A)
      Right singular vectors.
• template<typename Derived >
  cmat funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
      Functional calculus f(A)
• template<typename Derived >
  cmat sqrtm (const Eigen::MatrixBase< Derived > &A)
      Matrix square root.

    template<typename Derived >

  cmat absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.

    template < typename Derived >

  cmat expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.

    template<typename Derived >

  cmat logm (const Eigen::MatrixBase< Derived > &A)
      Matrix logarithm.

    template<typename Derived >

  cmat sinm (const Eigen::MatrixBase< Derived > &A)
     Matrix sin.

    template<typename Derived >

  cmat cosm (const Eigen::MatrixBase< Derived > &A)
• template<typename Derived >
  cmat spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > powm (const Eigen::MatrixBase< Derived > &A, idx n)
      Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.
• template<typename Derived >
  double schatten (const Eigen::MatrixBase< Derived > &A, double p)
      Schatten matrix norm.
 \bullet \ \ \mathsf{template} \mathord{<} \mathsf{typename} \ \mathsf{OutputScalar} \ \mathsf{,} \ \mathsf{typename} \ \mathsf{Derived} >
  dyn_mat< OutputScalar > cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const type-
  name Derived::Scalar &))
      Functor.
• template<typename T >
  dyn_mat< typename T::Scalar > kron (const T &head)
      Kronecker product.

    template<typename T, typename... Args>

  dyn mat< typename T::Scalar > kron (const T &head, const Args &... tail)
      Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > kron (const std::vector< Derived > &As)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > kron (const std::initializer_list< Derived > &As)
      Kronecker product.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
```

```
• template<typename T >
  dyn_mat< typename T::Scalar > dirsum (const T &head)
• template<typename T , typename... Args>
  dyn mat< typename T::Scalar > dirsum (const T &head, const Args &... tail)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > dirsum (const std::vector< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > dirsum (const std::initializer_list< Derived > &As)
     Direct sum.
• template<typename Derived >
  dyn mat< typename Derived::Scalar > dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > reshape (const Eigen::MatrixBase< Derived > &A, idx rows, idx
  cols)
     Reshape.
 template<typename Derived1 , typename Derived2 >
  dyn mat< typename Derived1::Scalar > comm (const Eigen::MatrixBase< Derived1 > &A, const Eigen::↔
  MatrixBase< Derived2 > &B)
     Commutator.
ullet template<typename Derived1 , typename Derived2 >
  dyn_mat< typename Derived1::Scalar > anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > prj (const Eigen::MatrixBase< Derived > &A)
     Projector.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > grams (const std::vector< Derived > &As)
     Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > grams (const std::initializer_list< Derived > &As)
     Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > grams (const Eigen::MatrixBase< Derived > &A)
     Gram-Schmidt orthogonalization.

    std::vector< idx > n2multiidx (idx n, const std::vector< idx > &dims)

     Non-negative integer index to multi-index.
• idx multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)
     Multi-index to non-negative integer index.

    ket mket (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Multi-partite qudit ket.

    ket mket (const std::vector< idx > &mask, idx d=2)

     Multi-partite qudit ket.

    cmat mprj (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Projector onto multi-partite qudit ket.

    cmat mprj (const std::vector < idx > &mask, idx d=2)

     Projector onto multi-partite qudit ket.
• template<typename InputIterator >
```

std::vector< double > abssq (InputIterator first, InputIterator last)

Computes the absolute values squared of an STL-like range of complex numbers.

• template<typename Container >

std::vector< double > abssq (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Computes the absolute values squared of an STL-like container.

template<typename Derived >

std::vector< double > abssq (const Eigen::MatrixBase< Derived > &A)

Computes the absolute values squared of an Eigen expression.

• template<typename InputIterator >

std::iterator_traits< InputIterator >::value_type sum (InputIterator first, InputIterator last)

Element-wise sum of an STL-like range.

• template<typename Container >

Container::value_type sum (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

std::iterator_traits< InputIterator >::value_type prod (InputIterator first, InputIterator last)

Element-wise product of an STL-like range.

• template<typename Container >

Container::value_type prod (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Element-wise product of the elements of an STL-like container.

template<typename Derived >

dyn col vect< typename Derived::Scalar > rho2pure (const Eigen::MatrixBase< Derived > &A)

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

std::vector< idx > complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

template<typename Derived >

std::vector< double > rho2bloch (const Eigen::MatrixBase< Derived > &A)

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

template<typename Derived >

```
std::size_t hash_eigen (const Eigen::MatrixBase< Derived > &A, std::size_t seed=0)
```

Computes the hash of en Eigen matrix/vector/expression.

template<typename Derived >

internal::IOManipEigen disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)

Eigen expression ostream manipulator.

• internal::IOManipEigen disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

• template<typename InputIterator >

internal::IOManipRange< InputIterator > disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")

Range ostream manipulator.

 $\bullet \ \ \text{template}{<} \text{typename Container} >$

internal::IOManipRange< typename Container::const_iterator > disp (const Container &c, const std::string &separator, const std::string &start="[", const std::string &end="]", typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

template<typename PointerType >

internal::IOManipPointer< PointerType > disp (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")

C-style pointer ostream manipulator.

template < typename Derived > void save (const Eigen::MatrixBase < Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.

• template<typename Derived >

dyn_col_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)

Generalized inner product.

• template<typename Derived >

dyn_col_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::

MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

• template<typename Derived >

std::tuple< std::vector< idx >, double, cmat > measure_seq (const Eigen::MatrixBase< Derived > &A, std::vector< idx > target, idx d=2)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< cplx > >::type loadMATLAB (const std::string &mat file, const std::string &var name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::

Scalar > >::type loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

std::vector< int > x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

• bigint gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > invperm (const std::vector< idx > &perm)

Inverse permutation.

std::vector< idx > compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

std::vector< bigint > factors (bigint a)

Prime factor decomposition.

bigint modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

• bigint modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple < bigint, bigint, bigint > egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

• bigint modiny (bigint a, bigint p)

Modular inverse of a mod p.

• bool isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

bigint randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

std::vector< std::pair< int, int > > convergents (const std::vector< int > &cf)

Convergents.

std::vector< std::pair< int, int > > convergents (double x, idx N)

Convergents.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, const
std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, idx
d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ↔ ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)
```

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

• template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, const std::vector< idx > &dims)
```

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

• template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, idx d=2)
```

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat kraus2super (const std::vector< cmat > &Ks)

Superoperator matrix.

cmat kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector< cmat > choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

template<typename Derived >

```
\frac{dyn\_mat}{<} typename \ Derived::Scalar > ptrace1 \ (const \ Eigen::MatrixBase < Derived > \&A, \ const \ std \hookleftarrow ::vector < idx > \&dims)
```

Partial trace.

template<typename Derived >

```
dyn_mat< typename Derived::Scalar > ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)
```

Partial trace.

• template<typename Derived >

 dyn_mat < typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, const std \leftarrow ::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector<
idx > &target, const std::vector< idx > &dims)

Partial trace.

template<typename Derived >

 $\label{localized_dyn_mat} $$ \down_mat< typename\ Derived::Scalar>ptrace\ (const\ Eigen::MatrixBase< Derived> &A,\ const\ std::vector< idx> &target,\ idx\ d=2) $$$

Partial trace.

template<typename Derived >

Partial transpose.

ullet template<typename Derived >

dyn_mat< typename Derived::Scalar > ptranspose (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial transpose.

template<typename Derived >

Subsystem permutation.

template<typename Derived >

dyn_mat< typename Derived::Scalar > syspermute (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &perm, idx d=2)

Subsystem permutation.

template<typename Derived >

dyn_mat< typename Derived::Scalar > applyQFT (const Eigen::MatrixBase< Derived > &A, const std↔ ::vector< idx > &target, idx d=2, bool swap=true)

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

ullet template<typename Derived >

dyn_mat< typename Derived::Scalar > applyTFQ (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2, bool swap=true)

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Qudit quantum Fourier transform.

• double rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

bigint rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

• idx randidx (idx a=std::numeric_limits < idx >::min(), idx b=std::numeric_limits < idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

• template<typename Derived >

Derived rand (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double a QPP_UNUSED_=0, double b QPP_UNUSED_=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

• template<>

```
dmat rand (idx rows, idx cols, double a, double b)
```

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

template<>

```
cmat rand (idx rows, idx cols, double a, double b)
```

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived randn (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double mean QPP_UNUSED_=0, double sigma QPP_UNUSED_=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

```
dmat randn (idx rows, idx cols, double mean, double sigma)
```

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

template<>

```
cmat randn (idx rows, idx cols, double mean, double sigma)
```

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

double randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

cmat randU (idx D=2)

Generates a random unitary matrix.

• cmat randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector < cmat > randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat randH (idx D=2)

Generates a random Hermitian matrix.

ket randket (idx D=2)

Generates a random normalized ket (pure state vector)

• cmat randrho (idx D=2)

Generates a random density matrix.

• std::vector < idx > randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.

std::vector< double > uniform (idx N)

Uniform probability distribution vector.

std::vector< double > marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > marginalY (const dmat &probXY)

Marginal distribution.

• template<typename Container >

double avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Average.

template<typename Container >
 double cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if<
 is_iterable< Container >::value >::type *=nullptr)

Covariance.

• template<typename Container >

double var (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Variance.

• template<typename Container >

double sigma (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Standard deviation.

• template<typename Container >

double cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Correlation.

Variables

constexpr double chop = 1e-10

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

• constexpr idx maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

constexpr double pi = 3.141592653589793238462643383279502884

 π

• constexpr double ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

constexpr double infty = std::numeric_limits<double>::max()

Used to denote infinity in double precision.

6.1.1 Detailed Description

Quantum++ main namespace.

6.1.2 Typedef Documentation

6.1.2.1 bigint

```
using qpp::bigint = typedef long long int
```

Big integer.

```
6.1.2.2 bra
```

```
using qpp::bra = typedef Eigen::RowVectorXcd
```

Complex (double precision) dynamic Eigen row vector.

6.1.2.3 cmat

```
using qpp::cmat = typedef Eigen::MatrixXcd
```

Complex (double precision) dynamic Eigen matrix.

6.1.2.4 cplx

```
using qpp::cplx = typedef std::complex<double>
```

Complex number in double precision.

6.1.2.5 dmat

```
using qpp::dmat = typedef Eigen::MatrixXd
```

Real (double precision) dynamic Eigen matrix.

6.1.2.6 dyn_col_vect

```
template<typename Scalar >
using qpp::dyn_col_vect = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, 1>
```

Dynamic Eigen column vector over the field specified by Scalar.

Example:

```
// type of colvect is Eigen::Matrix<float, Eigen::Dynamic, 1>
dyn_col_vect<float> colvect(2);
```

6.1.2.7 dyn_mat

```
template<typename Scalar >
using qpp::dyn_mat = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, Eigen::Dynamic>
```

Dynamic Eigen matrix over the field specified by Scalar.

Example:

```
// type of mat is Eigen::Matrix<float, Eigen::Dynamic, Eigen::Dynamic>
dyn_mat<float> mat(2, 3);
```

6.1.2.8 dyn_row_vect

```
template<typename Scalar >
using qpp::dyn_row_vect = typedef Eigen::Matrix<Scalar, 1, Eigen::Dynamic>
```

Dynamic Eigen row vector over the field specified by Scalar.

Example:

```
// type of rowvect is Eigen::Matrix<float, 1, Eigen::Dynamic>
dyn_row_vect<float> rowvect(3);
```

6.1.2.9 idx

```
using qpp::idx = typedef std::size_t
```

Non-negative integer index, make sure you use an unsigned type.

6.1.2.10 ket

```
using qpp::ket = typedef Eigen::VectorXcd
```

Complex (double precision) dynamic Eigen column vector.

6.1.2.11 to_void

```
template<typename... Ts>
using qpp::to_void = typedef typename make_void<Ts...>::type
```

Alias template that implements the proposal for void_t.

See also

```
http://www.open-std.org/jtc1/sc22/wg21/docs/papers/2014/n3911
```

6.1.3 Function Documentation

6.1.3.1 absm()

Matrix absolute value.

Parameters

```
A Eigen expression
```

Returns

Matrix absolute value of A

6.1.3.2 abssq() [1/3]

Computes the absolute values squared of an STL-like range of complex numbers.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Real vector consisting of the range absolute values squared

Computes the absolute values squared of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Real vector consisting of the container's absolute values squared

Computes the absolute values squared of an Eigen expression.

Parameters

```
A Eigen expression
```

Returns

Real vector consisting of the absolute values squared

6.1.3.5 adjoint()

Adjoint.

Parameters

```
A Eigen expression
```

Returns

Adjoint (Hermitian conjugate) of A, as a dynamic matrix over the same scalar field as A

6.1.3.6 anticomm()

Anti-commutator.

See also

qpp::comm()

Anti-commutator $\{A,B\} = AB + BA$. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
В	Eigen expression

Returns

Anti-commutator AB + BA, as a dynamic matrix over the same scalar field as A

6.1.3.7 apply() [1/5]

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

Returns

Gate A applied to the part target of state

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

Returns

Gate A applied to the part target of state

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*.

Parameters

Α	Eigen expression	
Ks	Set of Kraus operators	
target	target Subsystem indexes where the Kraus operators Ks are applied	
dims	Dimensions of the multi-partite system	

Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*.

Α	Eigen expression	
Ks	Set of Kraus operators	
target	Subsystem indexes where the Kraus operators Ks are applied	
d	Subsystem dimensions	

Returns

Output density matrix after the action of the channel

6.1.3.12 applyCTRL() [1/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate *A* must match the dimension of *target*. Also, all control subsystems in *ctrl* must have the same dimension.

Parameters

state	Eigen expression	
Α	Eigen expression	
ctrl	Control subsystem indexes	
target	Subsystem indexes where the gate A is applied	
dims	Dimensions of the multi-partite system	

Returns

CTRL-A gate applied to the part target of state

6.1.3.13 applyCTRL() [2/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

Returns

CTRL-A gate applied to the part target of state

6.1.3.14 applyQFT()

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

Parameters

Α		Eigen expression
tar	get	Subsystem indexes where the QFT is applied
d		Subsystem dimensions
SW	ар	Swaps the qubits/qudits at the end (true by default)

Qudit Quantum Fourier transform applied to the part target of A

6.1.3.15 applyTFQ()

Applies the inverse (adjoint) qudit quantum Fourier transform to the part *target* of the multi-partite state vector or density matrix *A*.

Parameters

Α	Eigen expression	
target	Subsystem indexes where the TFQ is applied	
d	Subsystem dimensions	
swap	Swaps the qubits/qudits at the end (true by default)	

Returns

Inverse (adjoint) qudit Quantum Fourier transform applied to the part target of A

6.1.3.16 avg()

Average.

Parameters

prob	Real probability vector representing the probability distribution of X
X	Real random variable values represented by an STL-like container

Returns

Average of X

6.1.3.17 bloch2rho()

Computes the density matrix corresponding to the 3-dimensional real Bloch vector *r*.

See also

qpp::rho2bloch()

Parameters

r 3-dimensional real vector

Returns

Qubit density matrix

6.1.3.18 choi2kraus()

Orthogonal Kraus operators from Choi matrix.

See also

qpp::kraus2choi()

Extracts a set of orthogonal (under Hilbert-Schmidt operator norm) Kraus operators from the Choi matrix A

Note

The Kraus operators satisfy $Tr(K_i^{\dagger}K_j) = \delta_{ij}$ for all $i \neq j$

Parameters

A Choi matrix

Returns

Set of orthogonal Kraus operators

6.1.3.19 choi2super()

Converts Choi matrix to superoperator matrix.

See also

qpp::super2choi()

Parameters

```
A Choi matrix
```

Returns

Superoperator matrix

6.1.3.20 comm()

Commutator.

See also

qpp::anticomm()

Commutator [A, B] = AB - BA. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
В	Eigen expression

Returns

Commutator AB-BA, as a dynamic matrix over the same scalar field as ${\it A}$

6.1.3.21 complement()

```
std::vector<idx> qpp::complement (
    std::vector< idx > subsys,
    idx n ) [inline]
```

Constructs the complement of a subsystem vector.

Parameters

subsys	Subsystem vector
n	Total number of systems

Returns

Complement of *subsys* with respect to the set $\{0, 1, \dots, n-1\}$

6.1.3.22 compperm()

Compose permutations.

Parameters

perm	Permutation
sigma	Permutation

Returns

Composition of the permutations *perm* o *sigma* = perm(sigma)

6.1.3.23 concurrence()

Wootters concurrence of the bi-partite qubit mixed state A.

Parameters

```
A Eigen expression
```

Wootters concurrence

6.1.3.24 conjugate()

Complex conjugate.

Parameters

```
A Eigen expression
```

Returns

Complex conjugate of A, as a dynamic matrix over the same scalar field as A

6.1.3.25 contfrac2x()

```
double qpp::contfrac2x ( const std::vector< int > & cf, idx N = idx(-1) ) [inline]
```

Real representation of a simple continued fraction.

See also

```
qpp::x2contfrac()
```

Note

If N is greater than the size of cf (by default it is), then all terms in cf are considered.

Parameters

Ci	•	Integer vector containing the simple continued fraction expansion
Ν		Number of terms considered in the continued fraction expansion.

Returns

Real representation of the simple continued fraction

```
6.1.3.26 convergents() [1/2]
```

```
std::vector<std::pair<int, int> > qpp::convergents ( const std::vector< int > & cf ) [inline]
```

Convergents.

See also

qpp::contfrac2x() and qpp::x2contfrac()

Parameters

```
cf Continued fraction
```

Returns

Vector of convergents pairs (a_k, b_k) that approximate the number represented by the continued fraction

6.1.3.27 convergents() [2/2]

Convergents.

See also

qpp::contfrac2x() and qpp::x2contfrac()

Note

In the continued fraction expansion of x has less terms than N, then the series of convergents is truncated to the number of terms in the continued fraction expansion of x.

Parameters

X	Real number
Ν	Number of convergents.

Returns

Vector of convergents pairs (a_k,b_k) that approximate the number x

6.1.3.28 cor()

Correlation.

Parameters

probXY	Real matrix representing the joint probability distribution of <i>X</i> and <i>Y</i> in lexicographical order (<i>X</i> labels the rows, <i>Y</i> labels the columns)	
Χ	Real random variable values represented by an STL-like container	
Y	Real random variable values represented by an STL-like container	

Returns

Correlation of X and Y

6.1.3.29 cosm()

Matrix cos.

Parameters

```
A Eigen expression
```

Returns

Matrix cosine of A

6.1.3.30 cov()

Covariance.

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X label the rows, Y labels the columns)	
X	Real random variable values represented by an STL-like container	
Y	Real random variable values represented by an STL-like container	

Returns

Covariance of X and Y

6.1.3.31 cwise()

Functor.

Parameters

Α	Eigen expression	
f	Pointer-to-function from scalars of A to OutputScalar	

Returns

Component-wise f(A), as a dynamic matrix over the ${\it OutputScalar}$ scalar field

6.1.3.32 det()

Determinant.

Parameters

```
A Eigen expression
```

Returns

Determinant of A, as a scalar over the same scalar field as A. Returns $\pm \infty$ when the determinant overflows/underflows.

Direct sum.

See also

qpp::dirsumpow()

Used to stop the recursion for the variadic template version of qpp::dirsum()

Parameters

head Eigen expression

Returns

Its argument head

6.1.3.34 dirsum() [2/4]

Direct sum.

See also

qpp::dirsumpow()

Parameters

head	Eigen expression	
tail	Variadic Eigen expression (zero or more parameters)]

Returns

Direct sum of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

See also

qpp::dirsumpow()

Parameters

As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}

Returns

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.3.37 dirsumpow()

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::dirsumpow (
```

```
const Eigen::MatrixBase< Derived > & A, idx n)
```

Direct sum power.

See also

qpp::dirsum()

Parameters

Α	Eigen expression
n	Non-negative integer

Returns

Direct sum of A with itself n times $A^{\oplus n}$, as a dynamic matrix over the same scalar field as A

Eigen expression ostream manipulator.

Parameters

Α	Eigen expression	
chop	Set to zero the elements smaller in absolute value than <i>chop</i>	

Returns

Instance of qpp::internal::IOManipEigen

Complex number ostream manipulator.

Z	Complex number (or any other type implicitly cast-able to std::complex <double>)</double>
chop Set to zero the elements smaller in absolute value than chop	

Returns

Instance of qpp::internal::IOManipEigen

Range ostream manipulator.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipRange

```
6.1.3.41 disp() [4/5]
```

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

С	Container
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipRange

const std::string & end = "]")

C-style pointer ostream manipulator.

Parameters

р	Pointer to the first element
N	Number of elements to be displayed
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipPointer

6.1.3.43 egcd()

Extended greatest common divisor of two integers.

See also

qpp::gcd()

а	Integer
b	Integer

Returns

Tuple of: 1. Integer m, 2. Integer n, and 3. Non-negative integer gcd(a,b) such that ma + nb = gcd(a,b)


6.1.3.44 eig()

Full eigen decomposition.

See also

qpp::heig()

Parameters



Returns

Pair of: 1. Eigenvalues of A, as a complex dynamic column vector, and 2. Eigenvectors of A, as columns of a complex dynamic matrix

6.1.3.45 entanglement() [1/2]

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

qpp::entropy()

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Entanglement, with the logarithm in base 2

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

qpp::entropy()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Entanglement, with the logarithm in base 2

6.1.3.47 entropy() [1/2]

von-Neumann entropy of the density matrix A

Parameters

A Eigen expression

von-Neumann entropy, with the logarithm in base 2

Shannon entropy of the probability distribution prob.

Parameters

```
prob Real probability vector
```

Returns

Shannon entropy, with the logarithm in base 2

6.1.3.49 evals()

Eigenvalues.

See also

qpp::hevals()

Parameters

```
A Eigen expression
```

Returns

Eigenvalues of A, as a complex dynamic column vector

6.1.3.50 evects()

Eigenvectors.

See also

qpp::hevects()

Parameters

```
A Eigen expression
```

Returns

Eigenvectors of A, as columns of a complex dynamic matrix

6.1.3.51 expm()

Matrix exponential.

Parameters

```
A Eigen expression
```

Returns

Matrix exponential of A

6.1.3.52 factors()

Prime factor decomposition.

Note

Runs in $\mathcal{O}(\sqrt{n})$ time complexity

Parameters

a Integer different from 0, 1 or -1

Integer vector containing the factors

6.1.3.53 funm()

Functional calculus f(A)

Parameters

Α	Eigen expression
f	Pointer-to-function from complex to complex

Returns

f(A)

Greatest common divisor of two integers.

See also

qpp::lcm()

Parameters

а	Integer
b	Integer

Returns

Greatest common divisor of a and b

```
6.1.3.55 gcd() [2/2]
bigint qpp::gcd (
              const std::vector< bigint > \& as ) [inline]
Greatest common divisor of a list of integers.
See also
     qpp::lcm()
Parameters
 as List of integers
Returns
     Greatest common divisor of all numbers in as
6.1.3.56 gconcurrence()
template<typename Derived >
double qpp::gconcurrence (
              const Eigen::MatrixBase< Derived > & A )
G-concurrence of the bi-partite pure state A.
Note
     Both local dimensions must be equal
Uses qpp::logdet() to avoid overflows
See also
     qpp::logdet()
Parameters
     Eigen expression
```

G-concurrence

Gram-Schmidt orthogonalization.

Parameters

As std::vector of Eigen expressions as column vectors

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

Gram-Schmidt orthogonalization.

Parameters

```
As std::initializer_list of Eigen expressions as column vectors
```

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

Gram-Schmidt orthogonalization.

Parameters

A Eigen expression, the input vectors are the columns of A

Gram-Schmidt vectors of the columns of A, as columns of a dynamic matrix over the same scalar field as A

6.1.3.60 hash_eigen()

Computes the hash of en Eigen matrix/vector/expression.

Note

Code taken from boost::hash_combine(), see https://www.boost.org/doc/libs/1_69_← 0/doc/html/hash/reference.html#boost.hash_combine

Parameters

Α	Eigen expression
seed	Seed, 0 by default

Returns

Hash of its argument

6.1.3.61 heig()

Full eigen decomposition of Hermitian expression.

See also

qpp::eig()

Parameters

A Eigen expression

Pair of: 1. Eigenvalues of A, as a real dynamic column vector, and 2. Eigenvectors of A, as columns of a complex dynamic matrix

6.1.3.62 hevals()

Hermitian eigenvalues.

See also

qpp::evals()

Parameters

A Eigen expression

Returns

Eigenvalues of Hermitian A, as a real dynamic column vector

6.1.3.63 hevects()

Eigenvectors of Hermitian matrix.

See also

qpp::evects()

Parameters

A Eigen expression

Returns

Eigenvectors of Hermitian matrix A, as columns of a complex matrix

6.1.3.64 inverse()

Inverse.

Parameters

```
A Eigen expression
```

Returns

Inverse of A, as a dynamic matrix over the same scalar field as A

6.1.3.65 invperm()

```
\label{eq:std:vector} $$ std::vector < idx > & perm ) $$ [inline] $$
```

Inverse permutation.

Parameters

perm	Permutation
------	-------------

Returns

Inverse of the permutation perm

6.1.3.66 ip() [1/2]

Generalized inner product.

Parameters

phi	Column vector Eigen expression
psi	Column vector Eigen expression
subsys	Subsystem indexes over which phi is defined
dims	Dimensions of the multi-partite system

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

Generalized inner product.

Parameters

phi	Column vector Eigen expression
psi	Column vector Eigen expression
subsys	Subsystem indexes over which phi is defined
d	Subsystem dimensions

Returns

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

6.1.3.68 isprime()

Primality test based on the Miller-Rabin's algorithm.

Parameters

р	Integer different from 0, 1 or -1
k	Number of iterations. The probability of a false positive is 2^{-k} .

Returns

True if the number is (most-likely) prime, false otherwise

6.1.3.69 kraus2choi()

Choi matrix.

See also

qpp::choi2kraus()

Constructs the Choi matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|,\,|0\rangle\langle 1|$ etc.

Note

The superoperator matrix S and the Choi matrix C are related by $S_{ab,mn}=C_{ma,nb}$

Parameters

Ks | Set of Kraus operators

Returns

Choi matrix

6.1.3.70 kraus2super()

Superoperator matrix.

Constructs the superoperator matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|$, $|0\rangle\langle 1|$ etc.

Parameters

Ks Set of Kraus operators

Returns

Superoperator matrix

Kronecker product.

See also

qpp::kronpow()

Used to stop the recursion for the variadic template version of app::kron()

Parameters

head	Eigen expression
------	------------------

Returns

Its argument head

```
6.1.3.72 kron() [2/4]
```

Kronecker product.

See also

qpp::kronpow()

Parameters

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

Returns

Kronecker product of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

As std::vector of Eigen expressions

Returns

Kronecker product of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Kronecker product.

See also

qpp::kronpow()

Parameters

As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}

Returns

Kronecker product of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.3.75 kronpow()

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::kronpow (
```

```
const Eigen::MatrixBase< Derived > & A, idx n)
```

Kronecker power.

See also

qpp::kron()

Parameters

Α	Eigen expression
n	Non-negative integer

Returns

Kronecker product of A with itself n times $A^{\otimes n}$, as a dynamic matrix over the same scalar field as A

Least common multiple of two integers.

See also

qpp::gcd()

Parameters

а	Integer
b	Integer

Returns

Least common multiple of a and b

Least common multiple of a list of integers.

See also

```
qpp::gcd()
```

Parameters

```
as List of integers
```

Returns

Least common multiple of all numbers in as

6.1.3.78 load()

Loads Eigen matrix from a binary file (internal format) in double precision.

See also

qpp::save()

The template parameter cannot be automatically deduced and must be explicitly provided, depending on the scalar field of the matrix that is being loaded.

Example:

```
// loads a previously saved Eigen dynamic complex matrix from "input.bin" cmat mat = load<cmat>("input.bin");
```

Parameters

```
fname Output file name
```

6.1.3.79 loadMATLAB() [1/2]

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

```
qpp::saveMATLAB()
```

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen ket
// from the MATLAB file "input.mat"
ket psi = loadMATLABket>("input.mat");
```

Template Parameters

Derived	Complex Eigen type
---------	--------------------

Parameters

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be loaded

Returns

Eigen dynamic matrix

6.1.3.80 loadMATLAB() [2/2]

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

```
qpp::saveMATLAB()
```

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen dynamic double matrix
// from the MATLAB file "input.mat"
dmat mat = loadMATLAB<dmat>("input.mat");
```

Template Parameters

Derived	Non-complex Eigen type
---------	------------------------

Parameters

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be loaded

Returns

Eigen dynamic matrix

6.1.3.81 logdet()

Logarithm of the determinant.

Useful when the determinant overflows/underflows

Parameters

```
A Eigen expression
```

Returns

Logarithm of the determinant of A, as a scalar over the same scalar field as A

6.1.3.82 logm()

Matrix logarithm.

Parameters

A Eigen expression

Matrix logarithm of A

Logarithmic negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Logarithmic negativity, with the logarithm in base 2

6.1.3.84 lognegativity() [2/2]

```
template<typename Derived >
double qpp::lognegativity (
          const Eigen::MatrixBase< Derived > & A,
          idx d = 2 )
```

Logarithmic negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Logarithmic negativity, with the logarithm in base 2

6.1.3.85 marginalX()

Marginal distribution.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels	
	the rows, Y labels the columns)	

Returns

Real vector consisting of the marginal distribution of X

6.1.3.86 marginalY()

Marginal distribution.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels	l
	the rows, Y labels the columns)	l

Returns

Real vector consisting of the marginal distribution of Y

6.1.3.87 measure() [1/9]

Measures the state vector or density operator A using the set of Kraus operators Ks.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.88 measure() [2/9]

Measures the state vector or density matrix A using the set of Kraus operators Ks.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.89 measure() [3/9]

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

Parameters

	Α	Eigen expression
ſ	U	Unitary matrix whose columns represent the measurement basis vectors

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.90 measure() [4/9]

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.91 measure() [5/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.93 measure() [7/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.94 measure() [8/9]

Measures the part *target* of the multi-partite state vector or density matrix *A* in the orthonormal basis or rank-1 projectors specified by the columns of the matrix *V*.

See also

```
qpp::measure_seq()
```

Note

The dimension of V must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Α	Eigen expression
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors
target Subsystem indexes that are measured	
dims	Dimensions of the multi-partite system

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

See also

```
qpp::measure_seq()
```

Note

The dimension of *V* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression	
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors	
target	Subsystem indexes that are measured	
d	Subsystem dimensions	

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

See also

qpp::measure()

Parameters

Α	Eigen expression
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

See also

qpp::measure()

Parameters

Α	Eigen expression
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|\text{mask}\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

Parameters

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

Returns

Multi-partite qudit state vector, as a complex dynamic column vector

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Multi-partite qudit state vector, as a complex dynamic column vector

6.1.3.100 modinv()

Modular inverse of a mod p.

See also

```
qpp::egcd()
```

Note

a and p must be co-prime

Parameters

а	Non-negative integer
р	Non-negative integer

Returns

```
Modular inverse a^{-1} \mod p
```

6.1.3.101 modmul()

Modular multiplication without overflow.

Computes $ab \bmod p$ without overflow

Parameters

а	Integer
b	Integer
р	Positive integer

Returns

 $ab \bmod p$ avoiding overflow

6.1.3.102 modpow()

```
bigint qpp::modpow (
          bigint a,
```

```
bigint n,
bigint p ) [inline]
```

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

Note

Uses qpp::modmul() that avoids overflows

Computes $a^n \bmod p$

Parameters

а	Non-negative integer
n	Non-negative integer
р	Strictly positive integer

Returns

```
a^n \bmod p
```

```
6.1.3.103 mprj() [1/2]
```

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|{\rm mask}\rangle$, where ${\it mask}$ is a std::vector of non-negative integers. Each element in ${\it mask}$ has to be smaller than the corresponding element in ${\it dims.}$

Parameters

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

6.1.3.105 multiidx2n()

Multi-index to non-negative integer index.

See also

```
qpp::n2multiidx()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

Parameters

midx	Multi-index
dims	Dimensions of the multi-partite system

Returns

Non-negative integer index

6.1.3.106 n2multiidx()

```
\label{eq:std::vector} $$ std::vector < idx > qpp::n2multiidx ($$ idx n,$$ const std::vector < idx > & dims ) [inline]
```

Non-negative integer index to multi-index.

See also

```
qpp::multiidx2n()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

Parameters

n	Non-negative integer index
dims	Dimensions of the multi-partite system

Returns

Multi-index of the same size as dims

6.1.3.107 negativity() [1/2]

Negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Negativity

6.1.3.108 negativity() [2/2]

```
template<typename Derived >
double qpp::negativity (
```

```
const Eigen::MatrixBase< Derived > & A, idx d = 2)
```

Negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Negativity

6.1.3.109 norm()

Frobenius norm.

Parameters

```
A Eigen expression
```

Returns

Frobenius norm of A

6.1.3.110 normalize()

Normalizes state vector (column or row vector) or density matrix.

```
A Eigen expression
```

Normalized state vector or density matrix

D-th root of unity.

Parameters

D Non-negative integer

Returns

D-th root of unity $\exp(2\pi i/D)$

User-defined literal for complex $i = \sqrt{-1}$ (real overload)

Example:

```
cplx z = 4.5_i; // type of z is std::complex<double>
```

6.1.3.113 powm()

Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

See also

```
qpp::spectralpowm()
```

Explicitly multiplies the matrix A with itself n times. By convention $A^0 = I$.

Parameters

Α	Eigen expression
n	Non-negative integer

Returns

Matrix power A^n , as a dynamic matrix over the same scalar field as A

6.1.3.114 prj()

Projector.

Normalized projector onto state vector

Parameters

```
A Eigen expression
```

Returns

Projector onto the state vector A, or the matrix Zero if A has norm zero, as a dynamic matrix over the same scalar field as A

6.1.3.115 prod() [1/3]

Element-wise product of A.

Parameters

```
A Eigen expression
```

Returns

Element-wise product of A, as a scalar over the same scalar field as A

Element-wise product of an STL-like range.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Element-wise product of the range, as a scalar over the same scalar field as the range

Element-wise product of the elements of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Element-wise product of the elements of the container, as a scalar over the same scalar field as the container

Partial trace.

See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Returns

Partial trace $Tr_{subsys}(\cdot)$ over the subsystems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

Partial trace.

See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial trace $Tr_{subsys}(\cdot)$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

```
6.1.3.120 ptrace1() [1/2]
```

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_A(\cdot)$ over the first subsytem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.121 ptrace1() [2/2]

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_A(\cdot)$ over the first subsystem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.122 ptrace2() [1/2]

Partial trace.

See also

```
qpp::ptrace1()
```

Partial trace over the second subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_B(\cdot)$ over the second subsytem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.123 ptrace2() [2/2]

Partial trace.

See also

qpp::ptrace1()

Partial trace over the second subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_B(\cdot)$ over the second subsytem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.124 ptranspose() [1/2]

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::ptranspose (
```

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & target,
const std::vector< idx > & dims )
```

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.3.125 ptranspose() [2/2]

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.3.126 QFT()

```
template<typename Derived >
dyn_col_vect<typename Derived::Scalar> qpp::QFT (
```

```
const Eigen::MatrixBase< Derived > & A, idx d = 2, bool swap = true)
```

Qudit quantum Fourier transform.

Parameters

Α	Eigen expression	
d	Subsystem dimensions	
swap	Swaps the qubits/qudits at the end (true by default)	

Returns

Qudit quantum Fourier transform applied on A

6.1.3.127 qmutualinfo() [1/2]

Quantum mutual information between 2 subsystems of a composite system.

Parameters

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
dims	Dimensions of the multi-partite system

Returns

Mutual information between the 2 subsystems

6.1.3.128 qmutualinfo() [2/2]

Quantum mutual information between 2 subsystems of a composite system.

Parameters

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
d	Subsystem dimensions

Returns

Mutual information between the 2 subsystems

Generates a random real number uniformly distributed in the interval [a, b)

Parameters

a	ì	Beginning of the interval, belongs to it
b)	End of the interval, does not belong to it

Returns

Random real number (double) uniformly distributed in the interval [a, b)

Generates a random big integer uniformly distributed in the interval [a, b].

Note

To avoid ambiguity with double qpp::rand(double, double) cast at least one of the arguments to qpp::bigint

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

Random big integer uniformly distributed in the interval [a, b]

Generates a random matrix with entries uniformly distributed in the interval [a, b)

If complex, then both real and imaginary parts are uniformly distributed in [a, b)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

```
6.1.3.132 rand() [4/5]

template<>>
dmat qpp::rand (
        idx rows ,
        idx cols ,
        double a ,
        double b ) [inline]
```

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries uniformly distributed in [-1,1)
dmat mat = rand<dmat>(3, 3, -1, 1);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Random real matrix

```
6.1.3.133 rand() [5/5]

template<>
cmat qpp::rand (
        idx rows ,
        idx cols ,
        double a ,
        double b ) [inline]
```

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd,
// with entries (both real and imaginary) uniformly distributed in [-1,1)
cmat mat = rand<cmat>(3, 3, -1, 1);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Returns

Random complex matrix

6.1.3.134 randH()

```
cmat qpp::randH (
    idx D = 2) [inline]
```

Generates a random Hermitian matrix.

Parameters

D Dimension of the Hilbert space

Random Hermitian matrix

6.1.3.135 randidx()

```
idx qpp::randidx (
        idx a = std::numeric_limits<idx>::min(),
        idx b = std::numeric_limits<idx>::max() ) [inline]
```

Generates a random index (idx) uniformly distributed in the interval [a, b].

Parameters

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

Returns

Random index (idx) uniformly distributed in the interval [a, b]

6.1.3.136 randket()

```
ket qpp::randket (
idx D = 2) [inline]
```

Generates a random normalized ket (pure state vector)

Parameters

```
D Dimension of the Hilbert space
```

Returns

Random normalized ket

6.1.3.137 randkraus()

```
std::vector<cmat> qpp::randkraus (
    idx N,
    idx D = 2 ) [inline]
```

Generates a set of random Kraus operators.

Note

The set of Kraus operators satisfy the closure condition $\sum_i K_i^\dagger K_i = I$

Parameters

Ν	Number of Kraus operators
D	Dimension of the Hilbert space

Returns

Set of N Kraus operators satisfying the closure condition

Generates a random matrix with entries normally distributed in N(mean, sigma)

If complex, then both real and imaginary parts are normally distributed in N(mean, sigma)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries normally distributed in N(0,2)
dmat mat = randn<dmat>(3, 3, 0, 2);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Returns

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd, 
// with entries (both real and imaginary) normally distributed in N(0,2) cmat mat = randn<cmat>(3, 3, 0, 2);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Returns

Random complex matrix

Generates a random real number (double) normally distributed in N(mean, sigma)

Parameters

mean	Mean
sigma	Standard deviation

Returns

Random real number normally distributed in N(mean, sigma)

6.1.3.142 randperm()

```
std::vector<idx> qpp::randperm (
    idx N ) [inline]
```

Generates a random uniformly distributed permutation.

Uses Knuth shuffle method (as implemented by std::shuffle), so that all permutations are equally probable

Parameters

```
N Size of the permutation
```

Returns

Random permutation of size N

6.1.3.143 randprime()

```
bigint qpp::randprime (
          bigint a,
          bigint b,
          idx N = 1000 ) [inline]
```

Generates a random big prime uniformly distributed in the interval [a, b].

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it
N	Maximum number of candidates

Random big integer uniformly distributed in the interval [a, b]

6.1.3.144 randprob()

```
\label{eq:continuous_double} $$\operatorname{double} : \operatorname{qpp}::\operatorname{randprob} ($$\operatorname{idx} N$) [inline]
```

Generates a random probability vector uniformly distributed over the probability simplex.

Parameters

N Size of the probability vector

Returns

Random probability vector

6.1.3.145 randrho()

```
cmat qpp::randrho (
    idx D = 2 ) [inline]
```

Generates a random density matrix.

Parameters

D Dimension of the Hilbert space

Returns

Random density matrix

6.1.3.146 randU()

```
cmat qpp::randU (
    idx D = 2) [inline]
```

Generates a random unitary matrix.

Parameters

D Dimension of the Hilbert space

Returns

Random unitary

6.1.3.147 randV()

Generates a random isometry matrix.

Parameters

Din	Size of the input Hilbert space
Dout	Size of the output Hilbert space

Returns

Random isometry matrix

```
6.1.3.148 renyi() [1/2]
```

Renyi- α entropy of the density matrix A, for $\alpha \geq 0.$

Note

When $\alpha \to 1$ the Renyi entropy converges to the von-Neumann entropy, with the logarithm in base 2

Α	Eigen expression
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

Renyi- α entropy, with the logarithm in base 2

Renyi- α entropy of the probability distribution *prob*, for $\alpha \geq 0$.

Note

When $\alpha \to 1$ the Renyi entropy converges to the Shannon entropy, with the logarithm in base 2

Parameters

prob	Real probability vector
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

Returns

Renyi- α entropy, with the logarithm in base 2

6.1.3.150 reshape()

Reshape.

Uses column-major order when reshaping (same as MATLAB)

Α	Eigen expression
rows	Number of rows of the reshaped matrix
cols	Number of columns of the reshaped matrix

Reshaped matrix with rows rows and cols columns, as a dynamic matrix over the same scalar field as A

6.1.3.151 rho2bloch()

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

See also

qpp::bloch2rho()

Note

It is implicitly assumed that the density matrix is Hermitian

Parameters

A Eigen expression

Returns

3-dimensional Bloch vector

6.1.3.152 rho2pure()

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

Note

No purity check is done, the input state A must have rank one, otherwise the function returns the first non-zero eigenvector of A

Parameters

A Eigen expression, assumed to be proportional to a projector onto a pure state, i.e. A is assumed to have rank one

The unique non-zero eigenvector of A (up to a phase), as a dynamic column vector over the same scalar field as A

6.1.3.153 save()

Saves Eigen expression to a binary file (internal format) in double precision.

See also

qpp::load()

Parameters

Α	Eigen expression
fname	Output file name

6.1.3.154 saveMATLAB() [1/2]

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

qpp::loadMATLAB()

Template Parameters

Complex Eigen type

Α	Eigen expression over the complex field
---	---

Parameters

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be saved
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details

6.1.3.155 saveMATLAB() [2/2]

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

qpp::loadMATLAB()

Template Parameters

igen type

Parameters

Α	Non-complex Eigen expression
mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be saved
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details

6.1.3.156 schatten()

Schatten matrix norm.

	Α	Eigen expression	
ſ	р	Real number, greater or equal to 1, use app::infty for $p = \infty$	

Schatten-p matrix norm of A

Schmidt basis on Alice side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix \boldsymbol{U} whose columns represent the Schmidt basis vectors on Alice side.

Schmidt basis on Alice side.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix U whose columns represent the Schmidt basis vectors on Alice side.

6.1.3.159 schmidtB() [1/2] template<typename Derived > cmat qpp::schmidtB (

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & dims )
```

Schmidt basis on Bob side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

Schmidt basis on Bob side.

idx d = 2)

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.162 schmidtcoeffs() [2/2]

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.163 schmidtprobs() [1/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.3.164 schmidtprobs() [2/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Parameters

,	Α	Eigen expression
(d	Subsystem dimensions

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.3.165 sigma()

Standard deviation.

Parameters

prob	Real probability vector representing the probability distribution of X
X	Real random variable values represented by an STL-like container

Returns

Standard deviation of X

6.1.3.166 sinm()

Matrix sin.

Parameters

A Eigen expression

Returns

Matrix sine of A

6.1.3.167 spectralpowm()

Matrix power.

See also

qpp::powm()

Uses the spectral decomposition of \emph{A} to compute the matrix power. By convention $\emph{A}^0 = \emph{I}$.

Parameters

Α	Eigen expression
Z	Complex number

Returns

Matrix power A^z

6.1.3.168 sqrtm()

Matrix square root.

Parameters

```
A Eigen expression
```

Returns

Matrix square root of A

```
6.1.3.169 sum() [1/3]
```

Element-wise sum of A.

Parameters

```
A Eigen expression
```

Returns

Element-wise sum of A, as a scalar over the same scalar field as A

```
6.1.3.170 sum() [2/3]
```

Element-wise sum of an STL-like range.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Element-wise sum of the range, as a scalar over the same scalar field as the range

Element-wise sum of the elements of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Element-wise sum of the elements of the container, as a scalar over the same scalar field as the container

6.1.3.172 super2choi()

Converts superoperator matrix to Choi matrix.

See also

qpp::choi2super()

Parameters

A Superoperator matrix

Returns

Choi matrix

6.1.3.173 svals()

Singular values.

Parameters

A Eigen expression

Returns

Singular values of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.174 svd()

Full singular value decomposition.

Parameters

A Eigen expression

Returns

Tuple of: 1. Left sigular vectors of A, as columns of a complex dynamic matrix, 2. Singular values of A, ordered in decreasing order, as a real dynamic column vector, and 3. Right singular vectors of A, as columns of a complex dynamic matrix

6.1.3.175 svdU()

Left singular vectors.

Parameters

```
A Eigen expression
```

Returns

Complex dynamic matrix, whose columns are the left singular vectors of A

6.1.3.176 svdV()

Right singular vectors.

Parameters

```
A Eigen expression
```

Returns

Complex dynamic matrix, whose columns are the right singular vectors of A

6.1.3.177 syspermute() [1/2]

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Parameters

Α	Eigen expression
perm	Permutation
dims	Dimensions of the multi-partite system

Returns

Permuted system, as a dynamic matrix over the same scalar field as A

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Parameters

Α	Eigen expression
perm	Permutation
d	Subsystem dimensions

Returns

Permuted system, as a dynamic matrix over the same scalar field as A

6.1.3.179 TFQ()

Inverse (adjoint) qudit quantum Fourier transform.

Parameters

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Inverse (adjoint) qudit quantum Fourier transform applied on A

6.1.3.180 trace()

Trace.

Parameters

```
A Eigen expression
```

Returns

Trace of A, as a scalar over the same scalar field as A

6.1.3.181 transpose()

Transpose.

Parameters

```
A Eigen expression
```

Returns

Transpose of A, as a dynamic matrix over the same scalar field as A

```
6.1.3.182 tsallis() [1/2] template<typename Derived > double qpp::tsallis ( const Eigen::MatrixBase< Derived > & A, double q)
```

Tsallis- q entropy of the density matrix A, for $q \ge 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the von-Neumann entropy, with the logarithm in base e

Parameters

Α	Eigen expression
q	Non-negative real number

Returns

Tsallis- q entropy

Tsallis- q entropy of the probability distribution prob, for $q \ge 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the Shannon entropy, with the logarithm in base e

Parameters

prob	Real probability vector
q	Non-negative real number

Returns

Tsallis- q entropy

6.1.3.184 uniform()

```
std::vector<double> qpp::uniform (
    idx N ) [inline]
```

Uniform probability distribution vector.

Parameters

N Size of the alphabet

Returns

Real vector consisting of a uniform distribution of size N

6.1.3.185 var()

Variance.

Parameters

prob	Real probability vector representing the probability distribution of X
Χ	Real random variable values represented by an STL-like container

Returns

Variance of X

6.1.3.186 x2contfrac()

Simple continued fraction expansion.

See also

```
qpp::contfrac2x()
```

Parameters

X	Real number
Ν	Maximum number of terms in the expansion
cut Stop the expansion when the next term is greater than	

Returns

Integer vector containing the simple continued fraction expansion of x. If there are M less than N terms in the expansion, a shorter vector with M components is returned.

6.1.4 Variable Documentation

6.1.4.1 chop

```
constexpr double qpp::chop = 1e-10
```

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

6.1.4.2 ee

```
constexpr double qpp::ee = 2.718281828459045235360287471352662497
```

Base of natural logarithm, e.

6.1.4.3 infty

```
constexpr double qpp::infty = std::numeric_limits<double>::max()
```

Used to denote infinity in double precision.

6.1.4.4 maxn

```
constexpr idx qpp::maxn = 64
```

Maximum number of allowed qubits/qudits (subsystems)

Used internally to allocate arrays on the stack (for performance reasons):

6.1.4.5 pi

```
constexpr double qpp::pi = 3.141592653589793238462643383279502884 \pi
```

6.2 qpp::exception Namespace Reference

Quantum++ exception hierarchy namespace.

Classes

class CustomException

Custom exception.

· class DimsInvalid

Invalid dimension(s) exception.

· class DimsMismatchCvector

Dimension(s) mismatch column vector size exception.

· class DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

· class DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

· class DimsMismatchVector

Dimension(s) mismatch vector size exception.

· class DimsNotEqual

Dimensions not equal exception.

class Duplicates

System (e.g. std::vector) has duplicates exception.

class Exception

Base class for generating Quantum++ custom exceptions.

· class InvalidIterator

Invalid iterator.

class MatrixMismatchSubsys

Matrix mismatch subsystems exception.

class MatrixNotCvector

Matrix is not a column vector exception.

· class MatrixNotRvector

Matrix is not a row vector exception.

class MatrixNotSquare

Matrix is not square exception.

class MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

class MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

class MatrixNotSquareNorVector

Matrix is not square nor vector exception.

class MatrixNotVector

Matrix is not a vector exception.

class NoCodeword

Codeword does not exist exception.

· class NotBipartite

Not bi-partite exception.

class NotImplemented

Code not yet implemented.

class NotQubitCvector

Column vector is not 2 x 1 exception.

class NotQubitMatrix

Matrix is not 2 x 2 exception.

class NotQubitRvector

Row vector is not 1 x 2 exception.

class NotQubitSubsys

Subsystems are not qubits exception.

· class NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

class OutOfRange

Argument out of range exception.

class PermInvalid

Invalid permutation exception.

class PermMismatchDims

Permutation mismatch dimensions exception.

· class QuditAlreadyMeasured

Qudit was already measured exception.

· class SizeMismatch

Size mismatch exception.

· class SubsysMismatchDims

Subsystems mismatch dimensions exception.

class TypeMismatch

Type mismatch exception.

class UndefinedType

Not defined for this type exception.

· class Unknown

Unknown exception.

· class ZeroSize

Object has zero size exception.

6.2.1 Detailed Description

Quantum++ exception hierarchy namespace.

6.3 qpp::experimental Namespace Reference

Experimental/test functions/classes, do not use or modify.

6.3.1 Detailed Description

Experimental/test functions/classes, do not use or modify.

6.4 qpp::internal Namespace Reference

Internal utility functions, do not use them directly or modify them.

Classes

- struct Display_Impl_
- · class EqualEigen

Functor for comparing Eigen expressions for equality.

· class HashEigen

Functor for hashing Eigen expressions.

- class IOManipEigen
- class IOManipPointer
- · class IOManipRange
- · class Singleton

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Functions

- template < class T >
 void hash combine (std::size t &seed, const T &v)
- void n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- template<typename Derived >

bool check square mat (const Eigen::MatrixBase< Derived > &A)

• template<typename Derived >

bool check vector (const Eigen::MatrixBase< Derived > &A)

ullet template<typename Derived >

bool check_rvector (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

bool check_cvector (const Eigen::MatrixBase< Derived > &A)

• template<typename T >

bool check_nonzero_size (const T &x) noexcept

• template<typename T1 , typename T2 >

bool check_matching_sizes (const T1 &lhs, const T2 &rhs) noexcept

- bool check_dims (const std::vector < idx > &dims)
- $\bullet \ \ \mathsf{template} \mathord{<} \mathsf{typename} \ \mathsf{Derived} >$

bool check_dims_match_mat (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ \mathsf{template}{<}\mathsf{typename} \ \mathsf{Derived}>$

bool check_dims_match_cvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ \text{template}{<} \text{typename Derived}>$

bool check_dims_match_rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- bool check_eq_dims (const std::vector< idx > &dims, idx dim) noexcept
- bool check_no_duplicates (std::vector < idx > v)
- bool check_subsys_match_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)
- template<typename Derived >

bool check_qubit_matrix (const Eigen::MatrixBase< Derived > &A) noexcept

 $\bullet \ \ \mathsf{template}{<}\mathsf{typename} \ \mathsf{Derived}>$

 $bool\ check_qubit_cvector\ (const\ Eigen::MatrixBase < Derived > \&A)\ noexcept$

template<typename Derived >

bool check_qubit_rvector (const Eigen::MatrixBase< Derived > &A) noexcept

• template<typename Derived >

 $bool\ check_qubit_vector\ (const\ Eigen::MatrixBase < Derived > \&A)\ no except$

- bool check_perm (const std::vector< idx > &perm)
- template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > kron2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::
 MatrixBase< Derived2 > &B)

```
    template<typename Derived1 , typename Derived2 > dyn_mat< typename Derived1::Scalar > dirsum2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen → ::MatrixBase< Derived2 > &B)
    template<typename T > void variadic_vector_emplace (std::vector< T > &)
    template<typename T , typename First , typename... Args> void variadic_vector_emplace (std::vector< T > &v, First &&first, Args &&... args)
    idx get_num_subsys (idx D, idx d)
    idx get_dim_subsys (idx sz, idx N)
```

6.4.1 Detailed Description

Internal utility functions, do not use them directly or modify them.

6.4.2 Function Documentation

6.4.2.1 check_cvector()

6.4.2.2 check_dims()

```
bool qpp::internal::check_dims (  \mbox{const std::vector} < \mbox{idx} > \& \mbox{dims} \mbox{)} \mbox{ [inline]}
```

6.4.2.3 check_dims_match_cvect()

6.4.2.4 check_dims_match_mat()

```
6.4.2.5 check_dims_match_rvect()
```

```
template<typename Derived >
bool qpp::internal::check_dims_match_rvect (
             const std::vector< idx > & dims,
             const Eigen::MatrixBase< Derived > & A )
6.4.2.6 check_eq_dims()
bool qpp::internal::check_eq_dims (
            const std::vector< idx > & dims,
             idx dim ) [inline], [noexcept]
6.4.2.7 check_matching_sizes()
template<typename T1 , typename T2 >
bool qpp::internal::check_matching_sizes (
            const T1 & lhs,
            const T2 & rhs ) [noexcept]
6.4.2.8 check_no_duplicates()
bool qpp::internal::check_no_duplicates (
             std::vector < idx > v) [inline]
6.4.2.9 check_nonzero_size()
template<typename T >
bool qpp::internal::check_nonzero_size (
            const T & x ) [noexcept]
6.4.2.10 check_perm()
```

bool qpp::internal::check_perm (

const std::vector< idx > & perm) [inline]

6.4.2.11 check_qubit_cvector()

```
template<typename Derived >
bool qpp::internal::check_qubit_cvector (
             const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.12 check_qubit_matrix()
template<typename Derived >
bool qpp::internal::check_qubit_matrix (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.13 check_qubit_rvector()
template<typename Derived >
bool qpp::internal::check_qubit_rvector (
             const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.14 check_qubit_vector()
template < typename Derived >
bool qpp::internal::check_qubit_vector (
             const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.15 check_rvector()
template<typename Derived >
bool qpp::internal::check_rvector (
             const Eigen::MatrixBase< Derived > & A )
6.4.2.16 check_square_mat()
template < typename Derived >
bool qpp::internal::check_square_mat (
            const Eigen::MatrixBase< Derived > & A )
```

```
6.4.2.17 check_subsys_match_dims()
```

```
bool qpp::internal::check_subsys_match_dims (
            const std::vector< idx > & subsys,
            const std::vector< idx > & dims ) [inline]
6.4.2.18 check_vector()
template<typename Derived >
bool qpp::internal::check_vector (
            const Eigen::MatrixBase< Derived > & A )
6.4.2.19 dirsum2()
template<typename Derived1 , typename Derived2 >
dyn_mat<typename Derived1::Scalar> qpp::internal::dirsum2 (
            const Eigen::MatrixBase< Derived1 > & A,
            const Eigen::MatrixBase< Derived2 > & B )
6.4.2.20 get_dim_subsys()
idx qpp::internal::get_dim_subsys (
            idx sz,
            idx N ) [inline]
6.4.2.21 get_num_subsys()
idx qpp::internal::get_num_subsys (
            idx D,
            idx d ) [inline]
6.4.2.22 hash_combine()
template<class T >
void qpp::internal::hash_combine (
```

std::size_t & seed,
const T & v)

6.4.2.23 kron2()

```
template<typename Derived1 , typename Derived2 >
dyn_mat<typename Derived1::Scalar> qpp::internal::kron2 (
             const Eigen::MatrixBase< Derived1 > & A,
             const Eigen::MatrixBase< Derived2 > & B )
6.4.2.24 multiidx2n()
idx qpp::internal::multiidx2n (
             const idx *const midx,
             idx numdims,
             const idx *const dims ) [inline], [noexcept]
6.4.2.25 n2multiidx()
void qpp::internal::n2multiidx (
             idx n,
             idx numdims,
             const idx *const dims,
             idx * result ) [inline], [noexcept]
6.4.2.26 variadic_vector_emplace() [1/2]
template<typename T >
void qpp::internal::variadic_vector_emplace (
            std::vector< T > & )
6.4.2.27 variadic_vector_emplace() [2/2]
template<typename T , typename First , typename... Args>
void qpp::internal::variadic_vector_emplace (
             std::vector< T > & v,
             First && first,
             Args &&... args )
```

6.5 qpp::literals Namespace Reference

Functions

```
• constexpr cplx operator"" _i (unsigned long long int x) noexcept \textit{User-defined literal for complex } i = \sqrt{-1} \textit{ (integer overload)}
```

```
template<char... Bits>
ket operator"" _ket ()
```

Multi-partite qubit ket user-defined literal.

template<char... Bits> bra operator"" _bra ()

Multi-partite qubit bra user-defined literal.

template<char... Bits> cmat operator"" _prj ()

Multi-partite qubit projector user-defined literal.

6.5.1 Function Documentation

```
6.5.1.1 operator"""_bra()

template<char... Bits>
bra qpp::literals::operator"" _bra ( )
```

Multi-partite qubit bra user-defined literal.

See also

```
qpp::mket() and qpp::adjoint()
```

Constructs the multi-partite qubit bra $\langle \mathrm{Bits}|$

Template Parameters

```
Bits String of binary numbers representing the qubit bra
```

Returns

Multi-partite qubit bra, as a complex dynamic row vector

User-defined literal for complex $i = \sqrt{-1}$ (integer overload)

Example:

```
cplx z = 4_i; // type of z is std::complex<double>
```

6.5.1.3 operator""" _ket()

```
template<char... Bits>
ket qpp::literals::operator"" _ket ( )
```

Multi-partite qubit ket user-defined literal.

See also

qpp::mket()

Constructs the multi-partite qubit ket |Bits>

Template Parameters

Returns

Multi-partite qubit ket, as a complex dynamic column vector

6.5.1.4 operator""" _prj()

```
template<char... Bits>
cmat qpp::literals::operator"" _prj ( )
```

Multi-partite qubit projector user-defined literal.

See also

qpp::mprj()

Constructs the multi-partite qubit projector $|\mathrm{Bits}\rangle\langle\mathrm{Bits}|$ (in the computational basis)

Template Parameters

Bits String of binary numbers representing the qubit state to project on

\mathbf{L}	ΔT	 rn	c

Multi-partite qubit projector, as a complex dynamic matrix

Chapter 7

Class Documentation

7.1 qpp::Bit_circuit Class Reference

Classical reversible circuit simulator.


#include <classes/reversible.h>

Inheritance diagram for qpp::Bit_circuit:



132 Class Documentation

Collaboration diagram for qpp::Bit_circuit:



Classes

class Gate_count

Gate counters.

· class Gate_depth

Gate depth.

Public Member Functions

• Bit_circuit (idx n)

Constructs a bit circuit instance.

• Bit_circuit (const Dynamic_bitset &dynamic_bitset)

Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.

• Bit_circuit & X (idx i)

Bit flip.

• Bit_circuit & NOT (idx i)

Bit flip

• Bit_circuit & CNOT (idx ctrl, idx target)

Controlled-NOT.

• Bit_circuit & TOF (idx i, idx j, idx k)

Toffoli gate.

• Bit_circuit & SWAP (idx i, idx j)

Swap bits.

• Bit_circuit & FRED (idx i, idx j, idx k)

Fredkin gate (Controlled-SWAP)

• Bit_circuit & reset () noexcept

Reset the circuit all zero, clear all gates.

Public Attributes

```
    class qpp::Bit_circuit::Gate_count gate_count
gate counters
```

```
    class qpp::Bit_circuit::Gate_depth * this
gate depths
```

Additional Inherited Members

7.1.1 Detailed Description

Classical reversible circuit simulator.

7.1.2 Constructor & Destructor Documentation

Constructs a bit circuit instance.

Parameters

n Number of classical bits

Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.

134 Class Documentation

Parameters

7.1.3 Member Function Documentation

7.1.3.1 CNOT()

Controlled-NOT.

Parameters

ctrl	Control bit index
target	Target bit index

Returns

Reference to the current instance

7.1.3.2 FRED()

```
Bit_circuit& qpp::Bit_circuit::FRED (
    idx i,
    idx j,
    idx k) [inline]
```

Fredkin gate (Controlled-SWAP)

Parameters

i	Control bit index	
j	j Target first bit index	
k Target second bit inde		

Returns

Reference to the current instance

```
7.1.3.3 NOT()
```

```
Bit_circuit& qpp::Bit_circuit::NOT (
        idx i ) [inline]
```

Bit flip.

See also

qpp::Bit_circuit::X()

Parameters

i Bit position in the circuit

Returns

Reference to the current instance

7.1.3.4 reset()

```
Bit_circuit& qpp::Bit_circuit::reset ( ) [inline], [noexcept]
```

Reset the circuit all zero, clear all gates.

Returns

Reference to the current instance

7.1.3.5 SWAP()

```
Bit_circuit& qpp::Bit_circuit::SWAP (
         idx i,
         idx j) [inline]
```

Swap bits.

Parameters

i	Bit index
i	Bit index

136 Class Documentation

Returns

Reference to the current instance

7.1.3.6 TOF()

```
Bit_circuit& qpp::Bit_circuit::TOF (
        idx i,
        idx j,
        idx k) [inline]
```

Toffoli gate.

Parameters

i	i Control first bit indexj Control second bit indexk Target bit index	
j		
k		

Returns

Reference to the current instance

7.1.3.7 X()

```
Bit_circuit& qpp::Bit_circuit::X (
        idx i) [inline]
```

Bit flip.

See also

```
qpp::Bit_circuit::NOT()
```

Parameters

```
i Bit position in the circuit
```

Returns

Reference to the current instance

7.1.4 Member Data Documentation

7.1.4.1 gate_count

```
class qpp::Bit_circuit::Gate_count qpp::Bit_circuit::gate_count
gate counters
```

7.1.4.2 this

```
class qpp::Bit_circuit::Gate_depth* qpp::Bit_circuit::this
gate depths
```

The documentation for this class was generated from the following file:


· classes/reversible.h

7.2 qpp::Codes Class Reference


const Singleton class that defines quantum error correcting codes

```
#include <classes/codes.h>
```

Inheritance diagram for qpp::Codes:



Collaboration diagram for qpp::Codes:



138 Class Documentation

Public Types

enum Type { Type::FIVE_QUBIT = 1, Type::SEVEN_QUBIT_STEANE, Type::NINE_QUBIT_SHOR }
 Code types, add more codes here if needed.

Public Member Functions

ket codeword (Type type, idx i) const
 Returns the codeword of the specified code type.

Private Member Functions

• Codes ()

Default constructor.

∼Codes ()=default

Default destructor.

Friends

class internal::Singleton < const Codes >

Additional Inherited Members

7.2.1 Detailed Description

const Singleton class that defines quantum error correcting codes

7.2.2 Member Enumeration Documentation

7.2.2.1 Type

```
enum qpp::Codes::Type [strong]
```

Code types, add more codes here if needed.

See also

qpp::Codes::codeword()

Enumerator

FIVE_QUBIT	[[5,1,3]] qubit code	
SEVEN_QUBIT_STEANE	[[7,1,3]] Steane qubit code	
NINE_QUBIT_SHOR	[[9,1,3]] Shor qubit code	

7.2.3 Constructor & Destructor Documentation

7.2.3.1 Codes()

```
qpp::Codes::Codes ( ) [inline], [private]
```

Default constructor.

7.2.3.2 ∼Codes()

```
qpp::Codes::~Codes ( ) [private], [default]
```

Default destructor.

7.2.4 Member Function Documentation

7.2.4.1 codeword()

Returns the codeword of the specified code type.

See also

```
qpp::Codes::Type
```

Parameters

type	Code type
i	Codeword index

Returns

i-th codeword of the code type

7.2.5 Friends And Related Function Documentation

140 Class Documentation

7.2.5.1 internal::Singleton < const Codes >

```
friend class internal::Singleton< const Codes > [friend]
```

The documentation for this class was generated from the following file:


· classes/codes.h

7.3 qpp::exception::CustomException Class Reference


Custom exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::CustomException:



Collaboration diagram for qpp::exception::CustomException:



Public Member Functions

• CustomException (const std::string &where, const std::string &what)

Private Member Functions

std::string type_description () const override
 Exception type description.

Private Attributes

std::string what_{{}}

7.3.1 Detailed Description

Custom exception.

Custom exception, the user must provide a custom message

7.3.2 Constructor & Destructor Documentation

142 Class Documentation

7.3.2.1 CustomException()

7.3.3 Member Function Documentation

7.3.3.1 type_description()

```
std::string qpp::exception::CustomException::type_description ( ) const [inline], [override],
[private], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

7.3.4 Member Data Documentation

7.3.4.1 what_

```
std::string qpp::exception::CustomException::what_ {} [private]
```

The documentation for this class was generated from the following file:


· classes/exception.h

7.4 qpp::exception::DimsInvalid Class Reference

Invalid dimension(s) exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsInvalid:



Collaboration diagram for qpp::exception::DimsInvalid:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.4.1 Detailed Description

Invalid dimension(s) exception.

std::vector<idx> of dimensions has zero size or contains zeros

7.4.2 Member Function Documentation

7.4.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.4.2.2 type_description()

std::string qpp::exception::DimsInvalid::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

7.5 qpp::exception::DimsMismatchCvector Class Reference


Dimension(s) mismatch column vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchCvector:



Collaboration diagram for qpp::exception::DimsMismatchCvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.5.1 Detailed Description

Dimension(s) mismatch column vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a column vector)

7.5.2 Member Function Documentation

7.5.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occur

7.5.2.2 type_description()

```
std::string qpp::exception::DimsMismatchCvector::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.6 qpp::exception::DimsMismatchMatrix Class Reference


Dimension(s) mismatch matrix size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchMatrix:



Collaboration diagram for qpp::exception::DimsMismatchMatrix:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.6.1 Detailed Description

Dimension(s) mismatch matrix size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of rows of the Eigen::Matrix (assumed to be a square matrix)

7.6.2 Member Function Documentation

7.6.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred

7.6.2.2 type_description()

```
std::string qpp::exception::DimsMismatchMatrix::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.7 qpp::exception::DimsMismatchRvector Class Reference


Dimension(s) mismatch row vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchRvector:



Collaboration diagram for qpp::exception::DimsMismatchRvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.7.1 Detailed Description

Dimension(s) mismatch row vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row vector)

7.7.2 Member Function Documentation

7.7.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.7.2.2 type_description()

std::string qpp::exception::DimsMismatchRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.8 qpp::exception::DimsMismatchVector Class Reference


Dimension(s) mismatch vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchVector:



Collaboration diagram for qpp::exception::DimsMismatchVector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.8.1 Detailed Description

Dimension(s) mismatch vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row/column vector)

7.8.2 Member Function Documentation

7.8.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

Text representing where the exception of	П
--	---

7.8.2.2 type_description()

```
std::string qpp::exception::DimsMismatchVector::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.9 qpp::exception::DimsNotEqual Class Reference


Dimensions not equal exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsNotEqual:



Collaboration diagram for qpp::exception::DimsNotEqual:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.9.1 Detailed Description

Dimensions not equal exception.

Local/global dimensions are not equal

7.9.2 Member Function Documentation

7.9.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.9.2.2 type_description()

std::string qpp::exception::DimsNotEqual::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

· classes/exception.h

7.10 qpp::internal::Display_Impl_ Struct Reference

```
#include <internal/util.h>
```

Inheritance diagram for qpp::internal::Display_Impl_:



Public Member Functions

template<typename T >
 std::ostream & display_impl_ (const T &A, std::ostream &os, double chop=qpp::chop) const

7.10.1 Member Function Documentation

7.10.1.1 display_impl_()

The documentation for this struct was generated from the following file:


• internal/util.h

7.11 qpp::exception::Duplicates Class Reference


System (e.g. std::vector) has duplicates exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Duplicates:



Collaboration diagram for qpp::exception::Duplicates:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.11.1 Detailed Description

System (e.g. std::vector) has duplicates exception.

7.11.2 Member Function Documentation

7.11.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.11.2.2 type_description()

```
std::string qpp::exception::Duplicates::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.12 qpp::Dynamic_bitset Class Reference


Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std:bitset < N >)

#include <classes/reversible.h>

Inheritance diagram for qpp::Dynamic_bitset:



Collaboration diagram for qpp::Dynamic_bitset:



Public Types

- using value_type = unsigned int type of the storage elements
- using storage_type = std::vector< value_type >
 type of the storage

Public Member Functions

• Dynamic_bitset (idx n)

Constructor, initializes all bits to false (zero)

virtual ~Dynamic bitset ()=default

Default virtual destructor.

const storage_type & data () const

Raw storage space of the bitset.

idx size () const noexcept

Number of bits stored in the bitset.

• idx storage_size () const noexcept

Size of the underlying storage space (in units of value_type, unsigned int by default)

· idx count () const noexcept

Number of bits set to one in the bitset (Hamming weight)

bool get (idx pos) const noexcept

The value of the bit at position pos.

· bool none () const noexcept

Checks whether none of the bits are set.

• bool all () const noexcept

Checks whether all bits are set.

• bool any () const noexcept

Checks whether any bit is set.

Dynamic_bitset & set (idx pos, bool value=true)

Sets the bit at position pos.

Dynamic_bitset & set () noexcept

Set all bits to true.

• Dynamic bitset & rand (idx pos, double p=0.5)

Sets the bit at position pos according to a Bernoulli(p) distribution.

• Dynamic_bitset & rand (double p=0.5)

Sets all bits according to a Bernoulli(p) distribution.

Dynamic_bitset & reset (idx pos)

Sets the bit at position pos to false.

Dynamic_bitset & reset () noexcept

Sets all bits to false.

Dynamic_bitset & flip (idx pos)

Flips the bit at position pos.

Dynamic_bitset & flip () noexcept

Flips all bits.

• bool operator== (const Dynamic_bitset &rhs) const noexcept

Equality operator.

bool operator!= (const Dynamic_bitset &rhs) const noexcept

Inequality operator.

• idx operator- (const Dynamic_bitset &rhs) const noexcept

Number of places the two bitsets differ (Hamming distance)

template < class CharT = char, class Traits = std::char_traits < CharT>, class Allocator = std::allocator < CharT>> std::basic_string < CharT, Traits, Allocator > to_string (CharT zero=CharT('0'), CharT one=CharT('1')) const String representation.

Protected Member Functions

```
    idx index_ (idx pos) const
    Index of the pos bit in the storage space.
```

idx offset_ (idx pos) const

Offset of the pos bit in the storage space relative to its index.

Protected Attributes

```
    idx storage_size_
        storage size
    idx n_
        number of bits
    std::vector < value_type > v_
        storage space
```

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display()* override, displays the bitset bit by bit

7.12.1 Detailed Description

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

7.12.2 Member Typedef Documentation

```
7.12.2.1 storage_type
using qpp::Dynamic_bitset::storage_type = std::vector<value_type>
type of the storage

7.12.2.2 value_type
using qpp::Dynamic_bitset::value_type = unsigned int
type of the storage elements
```

7.12.3 Constructor & Destructor Documentation

```
7.12.3.1 Dynamic_bitset()
```

Constructor, initializes all bits to false (zero)

Parameters

n Number of bits in the bitset

```
7.12.3.2 ~Dynamic_bitset()
```

```
virtual qpp::Dynamic_bitset::~Dynamic_bitset ( ) [virtual], [default]
```

Default virtual destructor.

7.12.4 Member Function Documentation

```
7.12.4.1 all()
```

```
bool qpp::Dynamic_bitset::all ( ) const [inline], [noexcept]
```

Checks whether all bits are set.

Returns

True if all of the bits are set

7.12.4.2 any()

```
bool qpp::Dynamic_bitset::any ( ) const [inline], [noexcept]
```

Checks whether any bit is set.

Returns

True if any of the bits is set

7.12.4.3 count()

```
idx qpp::Dynamic_bitset::count ( ) const [inline], [noexcept]
```

Number of bits set to one in the bitset (Hamming weight)

Returns

Hamming weight

7.12.4.4 data()

```
const storage_type& qpp::Dynamic_bitset::data ( ) const [inline]
```

Raw storage space of the bitset.

Returns

Const reference to the underlying storage space

7.12.4.5 display()

qpp::IDisplay::display() override, displays the bitset bit by bit

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.12.4.6 flip() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip (
        idx pos ) [inline]
```

Flips the bit at position pos.

Parameters

pos Position in the bitset

Returns

Reference to the current instance

```
7.12.4.7 flip() [2/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip ( ) [inline], [noexcept]
```

Flips all bits.

Returns

Reference to the current instance

7.12.4.8 get()

```
bool qpp::Dynamic_bitset::get (
          idx pos ) const [inline], [noexcept]
```

The value of the bit at position pos.

Parameters

pos Position in the bitset

Returns

The value of the bit at position pos

7.12.4.9 index_()

Index of the pos bit in the storage space.

Parameters

```
pos Bit location
```

Returns

Index of the pos bit in the storage space

7.12.4.10 none()

```
bool qpp::Dynamic_bitset::none ( ) const [inline], [noexcept]
```

Checks whether none of the bits are set.

Returns

True if none of the bits are set

7.12.4.11 offset_()

Offset of the pos bit in the storage space relative to its index.

Parameters

```
pos Bit location
```

Returns

Offset of the pos bit in the storage space relative to its index

7.12.4.12 operator"!=()

Inequality operator.

Parameters

```
rhs Dynamic_bitset against which the inequality is being tested
```

Returns

True if the bitsets are not equal (bit by bit), false otherwise

7.12.4.13 operator-()

Number of places the two bitsets differ (Hamming distance)

Parameters

rhs Dynamic_bitset against which the Hamming distance is computed

Returns

Hamming distance

7.12.4.14 operator==()

Equality operator.

Parameters

```
rhs Dynamic_bitset against which the equality is being tested
```

Returns

True if the bitsets are equal (bit by bit), false otherwise

7.12.4.15 rand() [1/2]

```
Dynamic_bitset& qpp::Dynamic_bitset::rand (
    idx pos,
    double p = 0.5 ) [inline]
```

Sets the bit at position *pos* according to a Bernoulli(p) distribution.

Parameters

pos	Position in the bitset
р	Probability

Returns

Reference to the current instance

Sets all bits according to a Bernoulli(p) distribution.

Parameters

```
p Probability
```

Returns

Reference to the current instance

Sets the bit at position pos to false.

Parameters

pos Position in the bitset	
----------------------------	--

Returns

Reference to the current instance

```
7.12.4.18 reset() [2/2]
Dynamic_bitset& qpp::Dynamic_bitset::reset ( ) [inline], [noexcept]
Sets all bits to false.
```

Returns

Reference to the current instance

```
7.12.4.19 set() [1/2]
```

Sets the bit at position pos.

Parameters

pos	Position in the bitset
value	Bit value

Returns

Reference to the current instance

```
7.12.4.20 set() [2/2]

Dynamic_bitset& qpp::Dynamic_bitset::set () [inline], [noexcept]
```

Set all bits to true.

Returns

Reference to the current instance

```
7.12.4.21 size()
```

```
idx qpp::Dynamic_bitset::size ( ) const [inline], [noexcept]
```

Number of bits stored in the bitset.

Returns

Number of bits stored in the bitset

```
7.12.4.22 storage_size()
```

```
idx qpp::Dynamic_bitset::storage_size ( ) const [inline], [noexcept]
```

Size of the underlying storage space (in units of value_type, unsigned int by default)

Returns

Size of the underlying storage space

7.12.4.23 to_string()

String representation.

Template Parameters

CharT	String character type	
Traits	String traits	
Allocator	String Allocator	

Parameters

	Character representing the zero
one	Character representing the one

Returns

The bitset as a string

7.12.5 Member Data Documentation

```
7.12.5.1 n_
idx qpp::Dynamic_bitset::n_ [protected]
```

7.12.5.2 storage_size_

number of bits

```
idx qpp::Dynamic_bitset::storage_size_ [protected]
```

storage size

```
7.12.5.3 v_
std::vector<value_type> qpp::Dynamic_bitset::v_ [protected]
storage space
```

The documentation for this class was generated from the following file:

· classes/reversible.h

7.13 qpp::internal::EqualEigen Class Reference

Functor for comparing Eigen expressions for equality.

```
#include <functions.h>
```

Public Member Functions

template<typename Derived >
 bool operator() (const Eigen::MatrixBase< Derived > &A, const Eigen::MatrixBase< Derived > &B) const

7.13.1 Detailed Description

Functor for comparing Eigen expressions for equality.

Note

Works without assertion fails even if the dimensions of the arguments are different (in which case simply returns false

7.13.2 Member Function Documentation

7.13.2.1 operator()()

The documentation for this class was generated from the following file:


· functions.h

7.14 qpp::exception::Exception Class Reference


Base class for generating Quantum++ custom exceptions.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Exception:



Collaboration diagram for qpp::exception::Exception:



Public Member Functions

- Exception (const std::string &where)
 - Constructs an exception.
- virtual const char * what () const noexcept override
 - Overrides std::exception::what()
- virtual std::string type_description () const =0
 - Exception type description.

Private Attributes

- std::string where_
- std::string msg_

7.14.1 Detailed Description

Base class for generating Quantum++ custom exceptions.

Derive from this class if more exceptions are needed, making sure to override qpp::exception::Exception::type_description() in the derived class and to inherit the constructor qpp::exception::Exception::Exception(). Preferably keep your newly defined exception classes in the namespace qpp::exception.

Example:

7.14.2 Constructor & Destructor Documentation

7.14.2.1 Exception()

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.14.3 Member Function Documentation

7.14.3.1 type_description()

```
std::string qpp::exception::Exception::type_description ( ) const [inline], [pure virtual]
```

Exception type description.

Returns

Exception type description

Implemented in qpp::exception::InvalidIterator, qpp::exception::NotImplemented, qpp::exception::CustomException, qpp::exception::Duplicates, qpp::exception::QuditAlreadyMeasured, qpp::exception::UndefinedType, qpp::exception::SizeMismatch, qpp::exception::TypeMismatch, qpp::exception::OutOfRange, qpp::exception::NotOdeword, qpp::exception::NotBipartite, qpp::exception::NotQubitSubsys, qpp::exception::NotQubitVector, qpp::exception::NotQubitRvector, qpp::exception::NotQubitCvector qpp::exception::NotQubitMatrix, qpp::exception::PermMismatchDims, qpp::exception::PermInvalid, qpp::exception::SubsysMismatchEqpp::exception::DimsMismatchVector, qpp::exception::DimsMismatchCvector, qpp::exception::DimsMismatchMatrix, qpp::exception::DimsNotEqual, qpp::exception::DimsInvalid, qpp::exception::MatrixMismatchSu qpp::exception::MatrixNotSquareNorVector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::Unknown.

7.14.3.2 what()

virtual const char* qpp::exception::Exception::what () const [inline], [override], [virtual],
[noexcept]

Overrides std::exception::what()

Returns

Exception description

7.14.4 Member Data Documentation

7.14.4.1 msg_

std::string qpp::exception::Exception::msg_ [mutable], [private]

7.14.4.2 where_

std::string qpp::exception::Exception::where_ [private]

The documentation for this class was generated from the following file:

· classes/exception.h

7.15 qpp::Bit_circuit::Gate_count Class Reference

Gate counters.

#include <classes/reversible.h>

Public Member Functions

• void reset ()

Resets the gate count.

Public Attributes

- idx NOT = 0
- idx & X = NOT
- idx CNOT = 0
- idx SWAP = 0
- idx FRED = 0
- idx TOF = 0
- idx total = 0

7.15.1 Detailed Description

Gate counters.

See also

```
qpp::Bit_circuit::Gate_depth
```

7.15.2 Member Function Documentation

```
7.15.2.1 reset()
```

```
void qpp::Bit_circuit::Gate_count::reset ( ) [inline]
```

Resets the gate count.

7.15.3 Member Data Documentation

7.15.3.1 CNOT

```
idx qpp::Bit_circuit::Gate_count::CNOT = 0
```

7.15.3.2 FRED

```
idx qpp::Bit_circuit::Gate_count::FRED = 0
```

7.15.3.3 NOT

```
idx qpp::Bit_circuit::Gate_count::NOT = 0
```

7.15.3.4 SWAP

```
idx qpp::Bit_circuit::Gate_count::SWAP = 0
```

7.15.3.5 TOF

```
idx qpp::Bit_circuit::Gate_count::TOF = 0
```

7.15.3.6 total

```
idx qpp::Bit_circuit::Gate_count::total = 0
```

7.15.3.7 X

```
idx& qpp::Bit_circuit::Gate_count::X = NOT
```

The documentation for this class was generated from the following file:


• classes/reversible.h

7.16 qpp::Bit_circuit::Gate_depth Class Reference

Gate depth.

#include <classes/reversible.h>

Collaboration diagram for qpp::Bit_circuit::Gate_depth:



Public Member Functions

• Gate depth (const Bit circuit &bit circuit)

Constructs the gate depth class out of a reversible bit circuit.

• Gate_depth (const Gate_depth &)=default

Default copy constructor.

Gate_depth & operator= (const Gate_depth &)=default

Default copy assignment operator.

Gate_depth (Gate_depth &&)=delete

Disables rvalue QCircuit.

• void reset ()

Resets the gate depth.

Public Attributes

- idx NOT = 0
- idx & X = NOT
- idx CNOT = 0
- idx SWAP = 0
- idx FRED = 0
- idx TOF = 0
- idx total = 0

Private Attributes

- friend Bit_circuit
- const Bit_circuit * bit_circuit_ {}
- · Dynamic bitset bNOT
- Dynamic_bitset bCNOT
- Dynamic_bitset bSWAP
- Dynamic_bitset bFRED
- Dynamic_bitset bTOF
- Dynamic_bitset btotal

7.16.1 Detailed Description

Gate depth.

See also

```
qpp::Bit_circuit::Gate_counter
```

7.16.2 Constructor & Destructor Documentation

```
7.16.2.1 Gate_depth() [1/3]
```

Constructs the gate depth class out of a reversible bit circuit.

Note

The reversible bit circuit must be an Ivalue

See also

```
qpp::Gate_depth(Gate_depth&&)
```

Parameters

```
bit_circuit Reversible bit circuit
```

```
7.16.2.2 Gate_depth() [2/3]
```

Default copy constructor.

Disables rvalue QCircuit.

7.16.3 Member Function Documentation

```
7.16.3.1 operator=()
```

Default copy assignment operator.

Returns

Reference to the current instance

```
7.16.3.2 reset()
```

```
void qpp::Bit_circuit::Gate_depth::reset ( ) [inline]
```

Resets the gate depth.

7.16.4 Member Data Documentation

7.16.4.1 bCNOT

```
Dynamic_bitset qpp::Bit_circuit::Gate_depth::bCNOT [private]
```

7.16.4.2 bFRED

```
Dynamic_bitset qpp::Bit_circuit::Gate_depth::bFRED [private]
7.16.4.3 Bit_circuit
friend qpp::Bit_circuit::Gate_depth::Bit_circuit [private]
7.16.4.4 bit_circuit_
const Bit_circuit* qpp::Bit_circuit::Gate_depth::bit_circuit_ {} [private]
7.16.4.5 bNOT
Dynamic_bitset qpp::Bit_circuit::Gate_depth::bNOT [private]
7.16.4.6 bSWAP
Dynamic_bitset qpp::Bit_circuit::Gate_depth::bSWAP [private]
7.16.4.7 bTOF
Dynamic_bitset qpp::Bit_circuit::Gate_depth::bTOF [private]
7.16.4.8 btotal
Dynamic_bitset qpp::Bit_circuit::Gate_depth::btotal [private]
7.16.4.9 CNOT
```

idx qpp::Bit_circuit::Gate_depth::CNOT = 0

7.16.4.10 FRED

```
idx qpp::Bit_circuit::Gate_depth::FRED = 0
```

7.16.4.11 NOT

```
idx qpp::Bit_circuit::Gate_depth::NOT = 0
```

7.16.4.12 SWAP

```
idx qpp::Bit_circuit::Gate_depth::SWAP = 0
```

7.16.4.13 TOF

```
idx qpp::Bit_circuit::Gate_depth::TOF = 0
```

7.16.4.14 total

```
idx qpp::Bit_circuit::Gate_depth::total = 0
```

7.16.4.15 X

```
idx& qpp::Bit_circuit::Gate_depth::X = NOT
```

The documentation for this class was generated from the following file:


• classes/reversible.h

7.17 qpp::Gates Class Reference


const Singleton class that implements most commonly used gates

#include <classes/gates.h>

Inheritance diagram for qpp::Gates:



Collaboration diagram for qpp::Gates:



Public Member Functions

- cmat Rn (double theta, const std::vector< double > &n) const

 Qubit rotation of theta about the 3-dimensional real (unit) vector n.
- cmat RX (double theta) const

Qubit rotation of theta about the X axis.

• cmat RY (double theta) const

Qubit rotation of theta about the Y axis.

cmat RZ (double theta) const

Qubit rotation of theta about the Z axis.

• cmat Zd (idx D=2) const

Generalized Z gate for qudits.

```
• cmat SWAPd (idx D=2) const
          SWAP gate for qudits.
    • cmat Fd (idx D=2) const
          Quantum Fourier transform gate for qudits.

    cmat MODMUL (idx a, idx N, idx n) const

          Modular multiplication gate for qubits Implements |x\rangle \longrightarrow |ax \bmod N\rangle.

    cmat Xd (idx D=2) const

          Generalized X gate for qudits.
    • template<typename Derived = Eigen::MatrixXcd>
      Derived Id (idx D=2) const
          Identity gate.

    template<typename Derived >

      dyn mat< typename Derived::Scalar > CTRL (const Eigen::MatrixBase< Derived > &A, const std::vector<
      idx > &ctrl, const std::vector < idx > &target, idx n, idx d=2) const
          Generates the multi-partite multiple-controlled-A gate in matrix form.

    template<typename Derived >

      dyn mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
      std::vector < idx > &dims) const
          Expands out.
    • template<typename Derived >
      dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
      std::initializer list< idx > &dims) const
          Expands out.

    template<typename Derived >

      dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, idx n,
      idx d=2) const
          Expands out.
    • std::string get_name (const cmat &U) const
          Get the name of the most common qubit gates.
Public Attributes
    • cmat Id2 {cmat::Identity(2, 2)}
          Identity gate.

    cmat H {cmat::Zero(2, 2)}

          Hadamard gate.
    cmat X {cmat::Zero(2, 2)}
          Pauli Sigma-X gate.

    cmat Y {cmat::Zero(2, 2)}

          Pauli Sigma-Y gate.

    cmat Z {cmat::Zero(2, 2)}

          Pauli Sigma-Z gate.

    cmat S {cmat::Zero(2, 2)}

          S gate.

    cmat T {cmat::Zero(2, 2)}

          T gate.

    cmat CNOT {cmat::Identity(4, 4)}

          Controlled-NOT control target gate.

    cmat CZ {cmat::Identity(4, 4)}

          Controlled-Phase gate.
    cmat CNOTba {cmat::Zero(4, 4)}
```

Controlled-NOT target->control gate.

cmat SWAP {cmat::Identity(4, 4)}

SWAP gate.

• cmat TOF {cmat::ldentity(8, 8)}

Toffoli gate.

• cmat FRED {cmat::ldentity(8, 8)}

Fredkin gate.

Private Member Functions

• Gates ()

Initializes the gates.

∼Gates ()=default

Default destructor.

Friends

class internal::Singleton < const Gates >

Additional Inherited Members

7.17.1 Detailed Description

const Singleton class that implements most commonly used gates

7.17.2 Constructor & Destructor Documentation

```
7.17.2.1 Gates()
```

```
qpp::Gates::Gates ( ) [inline], [private]
```

Initializes the gates.

7.17.2.2 \sim Gates()

```
qpp::Gates::\sim Gates () [private], [default]
```

Default destructor.

7.17.3 Member Function Documentation

7.17.3.1 CTRL()

Generates the multi-partite multiple-controlled-A gate in matrix form.

See also

```
qpp::applyCTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

Α	Eigen expression	
ctrl Control subsystem indexes		
target	Subsystem indexes where the gate A is applied	
n	Total number of subsystems	
d	Subsystem dimensions	

Returns

CTRL-A gate, as a matrix over the same scalar field as A

7.17.3.2 expandout() [1/3]

Expands out.

See also

```
qpp::kron()
```

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

A Eiger	Eigen expression	
	pos	Position
	dims	Dimensions of the multi-partite system

Returns

Tensor product $I \otimes \cdots \otimes I \otimes A \otimes I \otimes \cdots \otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.17.3.3 expandout() [2/3]

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Note

The std::initializer_list overload exists because otherwise, in the degenerate case when *dims* has only one element, the one element list is implicitly converted to the element's underlying type, i.e. qpp::idx, which has the net effect of picking the wrong (non-vector) qpp::expandout() overload

Parameters

Α	Eigen expression
pos	Position
dims	Dimensions of the multi-partite system

Returns

Tensor product $I \otimes \cdots \otimes I \otimes A \otimes I \otimes \cdots \otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.17.3.4 expandout() [3/3]

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

Α	Eigen expression
pos	Position
n	Number of subsystems
d	Subsystem dimensions

Returns

Tensor product $I \otimes \cdots \otimes I \otimes A \otimes I \otimes \cdots \otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.17.3.5 Fd()

```
cmat qpp::Gates::Fd (
    idx D = 2 ) const [inline]
```

Quantum Fourier transform gate for qudits.

Note

Defined as
$$F = \sum_{j,k=0}^{D-1} \exp(2\pi \mathrm{i} jk/D) |j\rangle\langle k|$$

Parameters

D Dimension of the Hilbert space

Returns

Fourier transform gate for qudits

7.17.3.6 get_name()

Get the name of the most common qubit gates.

Note

Assumes that the gate U is represented by a square matrix. If not, returns the empty string

Parameters

U | Complex matrix representing the quantum gate

Returns

The name of the gate (if any), otherwise the empty string

7.17.3.7 ld()

```
template<typename Derived = Eigen::MatrixXcd>
Derived qpp::Gates::Id (
    idx D = 2 ) const [inline]
```

Identity gate.

Note

Can change the return type from complex matrix (default) by explicitly specifying the template parameter

Parameters

D Dimension of the Hilbert space

Returns

Identity gate on a Hilbert space of dimension D

7.17.3.8 MODMUL()

```
cmat qpp::Gates::MODMUL (
    idx a,
```

```
idx N, idx n) const [inline]
```

Modular multiplication gate for qubits Implements $|x\rangle \longrightarrow |ax \bmod N\rangle$.

Note

For the gate to be unitary, *a* and *N* should be co-prime. The function does not check co-primality in release versions!

The number of qubits required to implement the gate should satisfy $n \geq \lceil \log_2(N) \rceil$

Parameters

а	Positive integer less than N
Ν	Positive integer
n	Number of qubits required for implementing the gate

Returns

Modular multiplication gate

7.17.3.9 Rn()

Qubit rotation of *theta* about the 3-dimensional real (unit) vector *n*.

Parameters

theta	Rotation angle
n	3-dimensional real (unit) vector

Returns

Rotation gate

7.17.3.10 RX()

Qubit rotation of theta about the X axis.

Parameters

theta	Rotation angle
-------	----------------

Returns

Rotation gate

7.17.3.11 RY()

Qubit rotation of theta about the Y axis.

Parameters

theta	Rotation angle
-------	----------------

Returns

Rotation gate

7.17.3.12 RZ()

Qubit rotation of theta about the Z axis.

Parameters

```
theta Rotation angle
```

Returns

Rotation gate

7.17.3.13 SWAPd()

```
cmat qpp::Gates::SWAPd (
        idx D = 2 ) const [inline]
```

SWAP gate for qudits.

Parameters

D Dimension of the Hilbert space

Returns

SWAP gate for qudits

7.17.3.14 Xd()

```
cmat qpp::Gates::Xd (
    idx D = 2 ) const [inline]
```

Generalized X gate for qudits.

Note

```
Defined as X=\sum_{j=0}^{D-1}|j\oplus 1\rangle\langle j|, i.e. raising operator X|j\rangle=|j\oplus 1\rangle
```

Parameters

D Dimension of the Hilbert space

Returns

Generalized X gate for qudits

7.17.3.15 Zd()

```
cmat qpp::Gates::Zd (
    idx D = 2 ) const [inline]
```

Generalized Z gate for qudits.

Note

Defined as
$$Z = \sum_{j=0}^{D-1} \exp(2\pi \mathrm{i} j/D) |j\rangle\langle j|$$

Parameters

D Dimension of the Hilbert space

Returns

Generalized Z gate for qudits

7.17.4 Friends And Related Function Documentation

```
7.17.4.1 internal::Singleton < const Gates >
friend class internal::Singleton < const Gates > [friend]
```

7.17.5 Member Data Documentation

```
7.17.5.1 CNOT
```

```
cmat qpp::Gates::CNOT {cmat::Identity(4, 4)}
```

Controlled-NOT control target gate.

7.17.5.2 CNOTba

```
cmat qpp::Gates::CNOTba {cmat::Zero(4, 4)}
```

Controlled-NOT target->control gate.

7.17.5.3 CZ

```
cmat qpp::Gates::CZ {cmat::Identity(4, 4)}
```

Controlled-Phase gate.

7.17.5.4 FRED

```
cmat qpp::Gates::FRED {cmat::Identity(8, 8)}
```

Fredkin gate.

```
7.17.5.5 H
cmat qpp::Gates::H {cmat::Zero(2, 2)}
Hadamard gate.
7.17.5.6 ld2
cmat qpp::Gates::Id2 {cmat::Identity(2, 2)}
Identity gate.
7.17.5.7 S
cmat qpp::Gates::S {cmat::Zero(2, 2)}
S gate.
7.17.5.8 SWAP
cmat qpp::Gates::SWAP {cmat::Identity(4, 4)}
SWAP gate.
7.17.5.9 T
cmat qpp::Gates::T {cmat::Zero(2, 2)}
T gate.
7.17.5.10 TOF
cmat qpp::Gates::TOF {cmat::Identity(8, 8)}
Toffoli gate.
```

7.17.5.11 X

```
cmat qpp::Gates::X {cmat::Zero(2, 2)}
```

Pauli Sigma-X gate.

7.17.5.12 Y

```
cmat qpp::Gates::Y {cmat::Zero(2, 2)}
```

Pauli Sigma-Y gate.

7.17.5.13 Z

```
cmat qpp::Gates::Z {cmat::Zero(2, 2)}
```

Pauli Sigma-Z gate.

The documentation for this class was generated from the following file:


· classes/gates.h

7.18 qpp::QCircuit::GateStep Struct Reference

One step consisting only of gates/operators in the circuit.

```
#include <classes/circuits/circuits.h>
```

Collaboration diagram for qpp::QCircuit::GateStep:



Public Member Functions

• GateStep ()=default

Default constructor.

GateStep (GateType gate_type, std::size_t gate_hash, const std::vector < idx > &ctrl, const std::vector < idx > &trl, const std::vector < idx > &target, std::string name="")

Constructs a gate step instance.

Public Attributes

```
    GateType gate_type_ = GateType::NONE
        gate type

            std::size_t gate_hash_
                 gate hash
            std::vector< idx > ctrl_
                  control

    std::vector< idx > target_
                  target where the gate is applied
    std::string name_
                  custom name of the step
```

7.18.1 Detailed Description

7.18.2.1 GateStep() [1/2]

One step consisting only of gates/operators in the circuit.

7.18.2 Constructor & Destructor Documentation

Constructs a gate step instance.

Parameters

gate_type	Gate type
gate_hash	Hash of the quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes
name	Optional gate name

7.18.3 Member Data Documentation

```
7.18.3.1 ctrl_
std::vector<idx> qpp::QCircuit::GateStep::ctrl_
control

7.18.3.2 gate_hash_
std::size_t qpp::QCircuit::GateStep::gate_hash_
gate hash

7.18.3.3 gate_type_
GateType qpp::QCircuit::GateStep::gate_type_ = GateType::NONE
gate type
```

```
7.18.3.4 name_
```

std::string qpp::QCircuit::GateStep::name_

custom name of the step

7.18.3.5 target_

```
std::vector<idx> qpp::QCircuit::GateStep::target_
```

target where the gate is applied

The documentation for this struct was generated from the following file:

· classes/circuits/circuits.h

7.19 qpp::internal::HashEigen Class Reference

Functor for hashing Eigen expressions.

```
#include <functions.h>
```

Public Member Functions

```
    template<typename Derived >
        std::size_t operator() (const Eigen::MatrixBase< Derived > &A) const
```

7.19.1 Detailed Description

Functor for hashing Eigen expressions.

7.19.2 Member Function Documentation

7.19.2.1 operator()()

The documentation for this class was generated from the following file:


• functions.h

7.20 qpp::IDisplay Class Reference

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

#include <classes/idisplay.h>

Inheritance diagram for qpp::IDisplay:



Public Member Functions

• IDisplay ()=default

Default constructor.

• IDisplay (const IDisplay &)=default

Default copy constructor.

• IDisplay (IDisplay &&)=default

Default move constructor.

IDisplay & operator= (const IDisplay &)=default

Default copy assignment operator.

IDisplay & operator= (IDisplay &&)=default

Default move assignment operator.

virtual ∼IDisplay ()=default

Default virtual destructor.

Private Member Functions

virtual std::ostream & display (std::ostream &os) const =0
 Must be overridden by all derived classes.

Friends

std::ostream & operator<< (std::ostream &os, const IDisplay &rhs)
 Overloads the extraction operator.

7.20.1 Detailed Description

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

This class defines friend inline std::ostream& operator<< (std::ostream& os, const qpp::IDisplay& rhs). The latter delegates the work to the pure private virtual function qpp::IDisplay::display() which has to be overridden by all derived classes.

7.20.2 Constructor & Destructor Documentation

```
7.20.2.1 IDisplay() [1/3]
qpp::IDisplay::IDisplay ( ) [default]
```

Default constructor.

Default copy constructor.

Default move constructor.

```
7.20.2.4 ~|Display()
virtual qpp::IDisplay::~IDisplay ( ) [virtual], [default]
```

Default virtual destructor.

7.20.3 Member Function Documentation

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implemented in qpp::QCircuit, qpp::QEngine, qpp::QCircuit::iterator::value_type_, qpp::Dynamic_bitset, qpp::internal::IOManipEigen, qpp::Timer< T, CLOCK_T >, qpp::internal::IOManipPointer< PointerType >, and qpp::internal::IOManipRange< InputIterator >.

Default copy assignment operator.

Default move assignment operator.

7.20.4 Friends And Related Function Documentation

Overloads the extraction operator.

Delegates the work to the virtual function qpp::IDisplay::display()

The documentation for this class was generated from the following file:


· classes/idisplay.h

7.21 qpp::IJSON Class Reference

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

#include <classes/idisplay.h>

Inheritance diagram for qpp::IJSON:



Public Member Functions

• IJSON ()=default

Default constructor.

• IJSON (const IJSON &)=default

Default copy constructor.

• IJSON (IJSON &&)=default

Default move constructor.

• IJSON & operator= (const IJSON &)=default

Default copy assignment operator.

IJSON & operator= (IJSON &&)=default

Default move assignment operator.

• virtual ∼IJSON ()=default

Default virtual destructor.

virtual std::string to_JSON (bool enclosed_in_curly_brackets=true) const =0

JSON representation of the derived instance, must be overridden by all derived classes.

7.21.1 Detailed Description

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

7.21.2 Constructor & Destructor Documentation

Default copy constructor.

Default move constructor.

```
7.21.2.4 ∼IJSON()
```

```
virtual qpp::IJSON::\simIJSON ( ) [virtual], [default]
```

Default virtual destructor.

7.21.3 Member Function Documentation

Default copy assignment operator.

```
7.21.3.2 operator=() [2/2]
```

Default move assignment operator.

7.21.3.3 to_JSON()

JSON representation of the derived instance, must be overridden by all derived classes.

Parameters

enclosed_in_curly_brackets	If true, encloses the result in curly brackets
----------------------------	--

Implemented in qpp::QCircuit, and qpp::QEngine.

The documentation for this class was generated from the following file:


· classes/idisplay.h

7.22 qpp::Init Class Reference


const Singleton class that performs additional initializations/cleanups

```
#include <classes/init.h>
```

Inheritance diagram for qpp::Init:



Collaboration diagram for qpp::Init:



Private Member Functions

• Init ()

Additional initializations.

• ∼Init ()

Cleanups.

Friends

- class internal::Singleton < const Init >

Additional Inherited Members

7.22.1 Detailed Description

const Singleton class that performs additional initializations/cleanups

7.22.2 Constructor & Destructor Documentation

7.22.2.1 Init()

```
qpp::Init::Init ( ) [inline], [private]
```

Additional initializations.

```
7.22.2.2 ∼Init()
```

```
qpp::Init::~Init ( ) [inline], [private]
```

Cleanups.

7.22.3 Friends And Related Function Documentation

```
7.22.3.1 internal::Singleton < const Init >
```

```
friend class internal::Singleton< const Init > [friend]
```

The documentation for this class was generated from the following file:


· classes/init.h

7.23 qpp::exception::InvalidIterator Class Reference


Invalid iterator.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::InvalidIterator:



Collaboration diagram for qpp::exception::InvalidIterator:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.23.1 Detailed Description

Invalid iterator.

7.23.2 Member Function Documentation

7.23.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.23.2.2 type_description()

std::string qpp::exception::InvalidIterator::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

· classes/exception.h


7.24 qpp::internal::IOManipEigen Class Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipEigen:



Collaboration diagram for qpp::internal::IOManipEigen:



Public Member Functions

- template<typename Derived > IOManipEigen (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
- IOManipEigen (const cplx z, double chop=qpp::chop)

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- cmat A_
- · double chop_

7.24.1 Constructor & Destructor Documentation

```
7.24.1.1 IOManipEigen() [1/2]
```

7.24.1.2 IOManipEigen() [2/2]

7.24.2 Member Function Documentation

7.24.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.24.3 Member Data Documentation

7.24.3.1 A_

```
cmat qpp::internal::IOManipEigen::A_ [private]
```

7.24.3.2 chop_

```
double qpp::internal::IOManipEigen::chop_ [private]
```


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


7.25 qpp::internal::IOManipPointer< PointerType > Class Template Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipPointer< PointerType >:



Collaboration diagram for qpp::internal::IOManipPointer< PointerType >:



Public Member Functions

- IOManipPointer (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")
- IOManipPointer (const IOManipPointer &)=default
- IOManipPointer & operator= (const IOManipPointer &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

```
const PointerType * p_
idx N_
std::string separator_
std::string start_
std::string end_
```

7.25.1 Constructor & Destructor Documentation

7.25.2 Member Function Documentation

7.25.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.25.2.2 operator=()

7.25.3 Member Data Documentation

```
7.25.3.1 end
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::end_ [private]
7.25.3.2 N_
template<typename PointerType>
idx qpp::internal::IOManipPointer< PointerType >::N_ [private]
7.25.3.3 p_
template<typename PointerType>
const PointerType* qpp::internal::IOManipPointer< PointerType >::p_ [private]
7.25.3.4 separator_
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::separator_ [private]
7.25.3.5 start_
template<typename PointerType>
```

The documentation for this class was generated from the following file:


std::string qpp::internal::IOManipPointer< PointerType >::start_ [private]

• internal/classes/iomanip.h


7.26 qpp::internal::IOManipRange < InputIterator > Class Template Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipRange< InputIterator >:



 $Collaboration\ diagram\ for\ qpp::internal::IOManipRange < Input Iterator >:$



Public Member Functions

- IOManipRange (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")
- IOManipRange (const IOManipRange &)=default
- IOManipRange & operator= (const IOManipRange &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- InputIterator first_
- InputIterator last
- std::string separator
- std::string start_
- · std::string end_

7.26.1 Constructor & Destructor Documentation

```
7.26.1.1 IOManipRange() [1/2]
```

7.26.1.2 IOManipRange() [2/2]

7.26.2 Member Function Documentation

7.26.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.26.2.2 operator=()

7.26.3 Member Data Documentation

```
7.26.3.1 end
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::end_ [private]
7.26.3.2 first_
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::first_ [private]
7.26.3.3 last_
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::last_ [private]
7.26.3.4 separator_
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::separator_ [private]
7.26.3.5 start_
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::start_ [private]
```

The documentation for this class was generated from the following file:


internal/classes/iomanip.h

7.27 qpp::is_complex< T > Struct Template Reference


Checks whether the type is a complex type.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_complex< T >:



Collaboration diagram for qpp::is_complex< T >:



7.27.1 Detailed Description

template < typename T > struct qpp::is_complex < T >

Checks whether the type is a complex type.

Provides the constant member *value* which is equal to *true*, if the type is a complex type, i.e. *std::complex<T>*

The documentation for this struct was generated from the following file:


· traits.h

7.28 qpp::is_complex < std::complex < T > > Struct Template Reference


Checks whether the type is a complex number type, specialization for complex types.

#include <traits.h>

Inheritance diagram for qpp::is_complex < std::complex < T > :



Collaboration diagram for qpp::is_complex< std::complex< T >>:



7.28.1 Detailed Description

template<typename T> struct qpp::is_complex< std::complex< T > >

Checks whether the type is a complex number type, specialization for complex types.

The documentation for this struct was generated from the following file:


· traits.h

7.29 qpp::is_iterable < T, typename > Struct Template Reference


Checks whether T is compatible with an STL-like iterable container.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_iterable < T, typename >:



Collaboration diagram for qpp::is_iterable < T, typename >:



7.29.1 Detailed Description

template<typename T, typename = void> struct qpp::is_iterable< T, typename >

Checks whether T is compatible with an STL-like iterable container.

Provides the constant member *value* which is equal to *true*, if *T* is compatible with an iterable container, i.e. provides at least *begin()* and *end()* member functions and allows de-referencing. Otherwise, *value* is equal to *false*.

The documentation for this struct was generated from the following file:


traits.h

7.30 qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().begin())) > Struct Template Reference


Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(*(std::declval < T >().begin())) > :



Collaboration diagram for qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std:: \leftarrow :declval< T >().end()), decltype(*(std::declval< T >().begin()))>>:



7.30.1 Detailed Description

 $\label{template} $$ \ensuremath{\mathsf{template}}$ $$ $ \ensuremath{\mathsf{template}}$ $$ $$ \ensuremath{\mathsf{template}}$ $$ $$ \ensuremath{\mathsf{template}}$ $$ $$ \ensuremath{\mathsf{template}}$ $$ \ensuremath{$

Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

The documentation for this struct was generated from the following file:

· traits.h

7.31 qpp::is_matrix_expression < Derived > Struct Template Reference


Checks whether the type is an Eigen matrix expression.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_matrix_expression< Derived >:



Collaboration diagram for qpp::is_matrix_expression< Derived >:



7.31.1 Detailed Description

template < typename Derived > struct qpp::is_matrix_expression < Derived >

Checks whether the type is an Eigen matrix expression.

Provides the constant member *value* which is equal to *true*, if the type is an Eigen matrix expression of type *Eigen ∷MatrixBase Oerived >*. Otherwise, *value* is equal to *false*.

The documentation for this struct was generated from the following file:


· traits.h

7.32 qpp::QCircuit::iterator Class Reference

Quantum circuit bound-checking (safe) iterator.

#include <classes/circuits/circuits.h>

Collaboration diagram for qpp::QCircuit::iterator:



Classes

· class value_type_

Value type class for qpp::QCircuit::iterator.

Public Types

• using difference_type = long long

iterator trait

• using value_type = value_type_

iterator trait

using pointer = const value_type *

iterator trait

• using reference = const value_type &

iterator trait

using iterator_category = std::forward_iterator_tag

iterator trait

Public Member Functions

• iterator ()=default

Default constructor.

• iterator (const iterator &)=default

Default copy constructor.

• iterator & operator= (const iterator &)=default

Default copy assignment operator.

iterator & operator++ ()

Prefix increment operator.

iterator operator++ (int)

Postfix increment operator.

```
    bool operator== (const iterator &rhs) const
Equality operator.
```

• bool operator!= (iterator rhs) const

Inequality operator.

• const value_type_ & operator* () const

Safe de-referencing operator.

void set_begin_ (const QCircuit *qc)

Sets the iterator to std::begin(this)

void set_end_ (const QCircuit *qc)

Sets the iterator to std::begin(this)

Private Attributes

```
const QCircuit * qc_ {nullptr}
```

< non-owning pointer to the parent const quantum circuit

value_type_ elem_ {nullptr}

7.32.1 Detailed Description

Quantum circuit bound-checking (safe) iterator.

Note

The iterator is a const_iterator by default

7.32.2 Member Typedef Documentation

7.32.2.1 difference_type

```
using qpp::QCircuit::iterator::difference_type = long long
```

iterator trait

7.32.2.2 iterator_category

```
using qpp::QCircuit::iterator::iterator_category = std::forward_iterator_tag
```

iterator trait

```
7.32.2.3 pointer
```

iterator trait

```
using qpp::QCircuit::iterator::pointer = const value_type*
```

7.32.2.4 reference

```
using qpp::QCircuit::iterator::reference = const value_type&
```

iterator trait

7.32.2.5 value_type

```
using qpp::QCircuit::iterator::value_type = value_type_
```

iterator trait

7.32.3 Constructor & Destructor Documentation

```
7.32.3.1 iterator() [1/2]

qpp::QCircuit::iterator::iterator ( ) [default]
```

Default constructor.

```
7.32.3.2 iterator() [2/2]
```

Default copy constructor.

7.32.4 Member Function Documentation

7.32.4.1 operator"!=()

Inequality operator.

Parameters

rhs Iterator against which the inequality is being tested

Returns

True if the iterators are not equal (bit by bit), false otherwise

```
7.32.4.2 operator*()
```

```
const value_type_& qpp::QCircuit::iterator::operator* ( ) const [inline]
```

Safe de-referencing operator.

Returns

Constant reference to the iterator element

```
7.32.4.3 operator++() [1/2]
```

```
iterator& qpp::QCircuit::iterator::operator++ ( ) [inline]
```

Prefix increment operator.

Returns

Reference to the current instance

```
7.32.4.4 operator++() [2/2]
```

Postfix increment operator.

Returns

Copy of the current instance before the increment

```
7.32.4.5 operator=()
```

Default copy assignment operator.

Returns

Reference to the current instance

```
7.32.4.6 operator==()
```

Equality operator.

Parameters

rhs | Iterator against which the equality is being tested

Returns

True if the iterators are equal, false otherwise

```
7.32.4.7 set_begin_()
```

Sets the iterator to std::begin(this)

Parameters

qc | Pointer to constant quantum circuit

```
7.32.4.8 set_end_()
```

Sets the iterator to std::begin(this)

Parameters

qc Pointer to constant quantum circuit

7.32.5 Member Data Documentation

```
7.32.5.1 elem_
value_type_ qpp::QCircuit::iterator::elem_ {nullptr} [private]

7.32.5.2 qc_
const QCircuit* qpp::QCircuit::iterator::qc_ {nullptr} [private]
```

< non-owning pointer to the parent const quantum circuit

The documentation for this class was generated from the following file:

• classes/circuits/circuits.h

7.33 qpp::make_void < Ts > Struct Template Reference

Helper for qpp::to_void<>> alias template.

```
#include <traits.h>
```

Public Types

• typedef void type

7.33.1 Detailed Description

```
template<typename... Ts>
struct qpp::make_void< Ts>
```

Helper for qpp::to_void<>> alias template.

See also

qpp::to_void<>

7.33.2 Member Typedef Documentation

7.33.2.1 type

```
template<typename... Ts>
typedef void qpp::make_void< Ts >::type
```

The documentation for this struct was generated from the following file:


· traits.h

7.34 qpp::exception::MatrixMismatchSubsys Class Reference


Matrix mismatch subsystems exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::MatrixMismatchSubsys:



Collaboration diagram for qpp::exception::MatrixMismatchSubsys:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.34.1 Detailed Description

Matrix mismatch subsystems exception.

Matrix size mismatch subsystem sizes (e.g. in qpp::apply())

7.34.2 Member Function Documentation

7.34.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

where	Text representing where the exception occurred
-------	--

7.34.2.2 type_description()

std::string qpp::exception::MatrixMismatchSubsys::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.35 qpp::exception::MatrixNotCvector Class Reference


Matrix is not a column vector exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Cvector:$



Collaboration diagram for qpp::exception::MatrixNotCvector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.35.1 Detailed Description

Matrix is not a column vector exception.

Eigen::Matrix is not a column vector

7.35.2 Member Function Documentation

7.35.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

where	Text representing where the exception occurred
-------	--

7.35.2.2 type_description()

std::string qpp::exception::MatrixNotCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.36 qpp::exception::MatrixNotRvector Class Reference


Matrix is not a row vector exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Rvector:$



Collaboration diagram for qpp::exception::MatrixNotRvector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.36.1 Detailed Description

Matrix is not a row vector exception.

Eigen::Matrix is not a row vector

7.36.2 Member Function Documentation

7.36.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

where	Text representing where the exception occurred
-------	--

7.36.2.2 type_description()

std::string qpp::exception::MatrixNotRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.37 qpp::exception::MatrixNotSquare Class Reference


Matrix is not square exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Square:$



Collaboration diagram for qpp::exception::MatrixNotSquare:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.37.1 Detailed Description

Matrix is not square exception.

Eigen::Matrix is not a square matrix

7.37.2 Member Function Documentation

7.37.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

where	Text representing where the exception occurred
-------	--

7.37.2.2 type_description()

std::string qpp::exception::MatrixNotSquare::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.38 qpp::exception::MatrixNotSquareNorCvector Class Reference


Matrix is not square nor column vector exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Square Nor Cvector:$



Collaboration diagram for qpp::exception::MatrixNotSquareNorCvector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.38.1 Detailed Description

Matrix is not square nor column vector exception.

Eigen::Matrix is not a square matrix nor a column vector

7.38.2 Member Function Documentation

7.38.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

where	Text representing where the exception occurred
-------	--

7.38.2.2 type_description()

```
std::string qpp::exception::MatrixNotSquareNorCvector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.39 qpp::exception::MatrixNotSquareNorRvector Class Reference


Matrix is not square nor row vector exception.

```
#include <classes/exception.h>
```

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Square Nor Rvector:$



Collaboration diagram for qpp::exception::MatrixNotSquareNorRvector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.39.1 Detailed Description

Matrix is not square nor row vector exception.

Eigen::Matrix is not a square matrix nor a row vector

7.39.2 Member Function Documentation

7.39.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

where Text representing where the exception occurred
--

7.39.2.2 type_description()

```
std::string qpp::exception::MatrixNotSquareNorRvector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.40 qpp::exception::MatrixNotSquareNorVector Class Reference


Matrix is not square nor vector exception.

```
#include <classes/exception.h>
```

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Square Nor Vector:$



Collaboration diagram for qpp::exception::MatrixNotSquareNorVector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.40.1 Detailed Description

Matrix is not square nor vector exception.

Eigen::Matrix is not a square matrix nor a row/column vector

7.40.2 Member Function Documentation

7.40.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

where	Text representing where the exception occurred	1
-------	--	---

7.40.2.2 type_description()

```
std::string qpp::exception::MatrixNotSquareNorVector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.41 qpp::exception::MatrixNotVector Class Reference


Matrix is not a vector exception.

```
#include <classes/exception.h>
```

 $Inheritance\ diagram\ for\ qpp::exception::MatrixNotVector:$



Collaboration diagram for qpp::exception::MatrixNotVector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.41.1 Detailed Description

Matrix is not a vector exception.

Eigen::Matrix is not a row or column vector

7.41.2 Member Function Documentation

7.41.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

where	Text representing where the exception occurred
	Toxi representing where the exception eccurred

7.41.2.2 type_description()

std::string qpp::exception::MatrixNotVector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.42 qpp::QCircuit::MeasureStep Struct Reference

One step consisting only of measurements in the circuit.

#include <classes/circuits/circuits.h>

 $Collaboration\ diagram\ for\ qpp:: QCircuit:: Measure Step:$



Public Member Functions

• MeasureStep ()=default

Default constructor.

MeasureStep (MeasureType measurement_type, const std::vector< std::size_t > &mats_hash, const std
 ::vector< idx > &target, idx c_reg, std::string name="")

Constructs a measurement step instance.

Public Attributes

MeasureType measurement_type_ = MeasureType::NONE

measurement type

- std::vector< std::size t > mats hash
- std::vector < idx > target_

target where the measurement is applied

- idx c_reg_ {}
- · std::string name_

custom name of the step

7.42.1 Detailed Description

One step consisting only of measurements in the circuit.

7.42.2 Constructor & Destructor Documentation

```
7.42.2.1 MeasureStep() [1/2]

qpp::QCircuit::MeasureStep::MeasureStep ( ) [default]
```

Default constructor.

7.42.2.2 MeasureStep() [2/2]

Constructs a measurement step instance.

measurement_type	Measurement type
mats_hash	Vector of hashes of the measurement matrix/matrices
target	Target qudit indexes
c_reg	Classical register where the value of the measurement is stored
name	Optional gate name

7.42.3 Member Data Documentation

```
7.42.3.1 c_reg_
idx qpp::QCircuit::MeasureStep::c_reg_ {}
index of the classical register where the measurement result is being stored
7.42.3.2 mats_hash_
std::vector<std::size_t> qpp::QCircuit::MeasureStep::mats_hash_
hashes of measurement matrix/matrices
7.42.3.3 measurement_type_
MeasureType qpp::QCircuit::MeasureStep::measurement_type_ = MeasureType::NONE
measurement type
7.42.3.4 name_
std::string qpp::QCircuit::MeasureStep::name_
custom name of the step
```

7.42.3.5 target_

std::vector<idx> qpp::QCircuit::MeasureStep::target_

target where the measurement is applied

The documentation for this struct was generated from the following file:


• classes/circuits/circuits.h

7.43 qpp::exception::NoCodeword Class Reference


Codeword does not exist exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NoCodeword:



Collaboration diagram for qpp::exception::NoCodeword:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.43.1 Detailed Description

Codeword does not exist exception.

Codeword does not exist, thrown when calling qpp::Codes::codeword() with an invalid index

7.43.2 Member Function Documentation

7.43.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.43.2.2 type_description()

```
std::string qpp::exception::NoCodeword::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.44 qpp::NoiseBase < T > Class Template Reference

Base class for all noise models, derive your particular noise model.

```
#include <classes/noise.h>
```

Collaboration diagram for qpp::NoiseBase< T >:



Public Types

• using noise_type = T

Public Member Functions

template<typename U = noise_type>
 NoiseBase (const std::vector< cmat > &Ks, typename std::enable_if< std::is_same< NoiseType::StateDependent,
 U >::value >::type *=nullptr)

Constructs a noise instance for StateDependent noise type.

• template<typename U = noise_type>

NoiseBase (const std::vector < cmat > &Ks, const std::vector < double > &probs, typename std::enable_if < std::is_same < NoiseType::StateIndependent, U >::value >::type *=nullptr)

Constructs a noise instance for StateIndependent noise type.

virtual ∼NoiseBase ()=default

Default virtual destructor.

• idx get_d () const noexcept

Qudit dimension.

std::vector< cmat > get_Ks () const

Vector of noise operators.

• std::vector< double > get_probs () const

Vector of probabilities corresponding to each noise operator.

• idx get_last_idx () const

Index of the last occurring noise element.

double get_last_p () const

Probability of the last occurring noise element.

cmat get_last_K () const

Last occurring noise element.

- virtual cmat operator() (const cmat &state) const
 - Function invocation operator, applies the underlying noise model on the state vector or density matrix state.
- virtual cmat operator() (const cmat &state, idx target) const
 - Function invocation operator, applies the underlying noise model on qudit target of the multi-partite state vector or density matrix state.
- virtual cmat operator() (const cmat &state, const std::vector< idx > &target) const
 - Function invocation operator, applies the underlying correlated noise model on qudits specified by target of the multipartite state vector or density matrix state.

Protected Member Functions

- void compute_probs_ (const cmat &state, const std::vector < idx > &target) const
 Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)
- cmat compute_state_ (const cmat &state, const std::vector < idx > &target) const
 Compute the resulting state after the noise was applied.

Protected Attributes

- const std::vector < cmat > Ks_
 - Kraus operators.
- std::vector< double > probs_
 - probabilities
- idx d_ {}
 - qudit dimension
- idx i_{}

index of the last occurring noise element

bool generated_ {false}

invoked, or if the noise is state-independent

7.44.1 Detailed Description

```
template < class T> class qpp::NoiseBase < T >
```

Base class for all noise models, derive your particular noise model.

7.44.2 Member Typedef Documentation

7.44.2.1 noise_type

```
template<class T>
using qpp::NoiseBase< T >::noise_type = T
```

7.44.3 Constructor & Destructor Documentation

Constructs a noise instance for StateDependent noise type.

Note

SFINAEd-out for StateIndependent noise

Parameters

Ks Vector of noise (Kraus) operators that specify the noise

7.44.3.2 NoiseBase() [2/2]

Constructs a noise instance for StateIndependent noise type.

Note

SFINAEd-out for StateDependent noise

Parameters

Ks	Vector of noise (Kraus) operators that specify the noise
probs	Vector of probabilities corresponding to each Kraus operator

7.44.3.3 ∼NoiseBase()

```
template<class T>
virtual qpp::NoiseBase< T >::~NoiseBase ( ) [virtual], [default]
```

Default virtual destructor.

7.44.4 Member Function Documentation

7.44.4.1 compute_probs_()

Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

Parameters

state	State vector or density matrix
target	Qudit indexes where the noise is applied

7.44.4.2 compute_state_()

Compute the resulting state after the noise was applied.

Parameters

state	State vector or density matrix
target	Qudit indexes where the noise is applied

Returns

Resulting state after the noise was applied

```
7.44.4.3 get_d()
```

```
template<class T>
idx qpp::NoiseBase< T >::get_d ( ) const [inline], [noexcept]
```

Qudit dimension.

Returns

Qudit dimension

```
7.44.4.4 get_Ks()
```

```
template<class T>
std::vector<cmat> qpp::NoiseBase< T >::get_Ks () const [inline]
```

Vector of noise operators.

Returns

Vector of noise operators

7.44.4.5 get_last_idx()

```
template<class T>
idx qpp::NoiseBase< T >::get_last_idx ( ) const [inline]
```

Index of the last occurring noise element.

Returns

Index of the last occurring noise element

```
7.44.4.6 get_last_K()
```

```
template<class T>
cmat qpp::NoiseBase< T >::get_last_K ( ) const [inline]
```

Last occurring noise element.

Returns

Last occurring noise element

7.44.4.7 get_last_p()

```
template<class T>
double qpp::NoiseBase< T >::get_last_p ( ) const [inline]
```

Probability of the last occurring noise element.

Returns

Probability of the last occurring noise element

7.44.4.8 get_probs()

```
template<class T>
std::vector<double> qpp::NoiseBase< T >::get_probs ( ) const [inline]
```

Vector of probabilities corresponding to each noise operator.

Returns

Probability vector

7.44.4.9 operator()() [1/3]

Function invocation operator, applies the underlying noise model on the state vector or density matrix state.

Parameters

```
state State vector or density matrix
```

Returns

Resulting state vector or density matrix

7.44.4.10 operator()() [2/3]

```
template<class T>
virtual cmat qpp::NoiseBase< T >::operator() (
```

```
const cmat & state,
idx target ) const [inline], [virtual]
```

Function invocation operator, applies the underlying noise model on qudit *target* of the multi-partite state vector or density matrix *state*.

Parameters

state	Multi-partite state vector or density matrix
target	Qudit index where the noise is applied

Returns

Resulting state vector or density matrix

Function invocation operator, applies the underlying correlated noise model on qudits specified by *target* of the multi-partite state vector or density matrix *state*.

Parameters

state	Multi-partite state vector or density matrix
target	Qudit indexes where the correlated noise is applied

Returns

Resulting state vector or density matrix

7.44.5 Member Data Documentation

7.44.5.1 d_

```
template<class T>
idx qpp::NoiseBase< T >::d_ {} [mutable], [protected]
```

qudit dimension

7.44.5.2 generated_

```
template<class T>
bool qpp::NoiseBase< T >::generated_ {false} [mutable], [protected]
```

invoked, or if the noise is state-independent

set to true after compute_state_() is

7.44.5.3 i_

```
template<class T>
idx qpp::NoiseBase< T >::i_ {} [mutable], [protected]
```

index of the last occurring noise element

7.44.5.4 Ks_

```
template<class T>
const std::vector<cmat> qpp::NoiseBase< T >::Ks_ [protected]
```

Kraus operators.

7.44.5.5 probs_

```
template<class T>
std::vector<double> qpp::NoiseBase< T >::probs_ [mutable], [protected]
```

probabilities

The documentation for this class was generated from the following file:

· classes/noise.h

7.45 qpp::NoiseType Class Reference

Contains template tags used to specify the noise type.

```
#include <classes/noise.h>
```

Classes

· class StateDependent

Template tag, used whenever the noise is state-dependent.

• class StateIndependent

Template tag, used whenever the noise is state-independent.

7.45.1 Detailed Description

Contains template tags used to specify the noise type.

The documentation for this class was generated from the following file:


· classes/noise.h

7.46 qpp::exception::NotBipartite Class Reference


Not bi-partite exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotBipartite:



Collaboration diagram for qpp::exception::NotBipartite:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.46.1 Detailed Description

Not bi-partite exception.

std::vector<idx> of dimensions has size different from 2

7.46.2 Member Function Documentation

7.46.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.46.2.2 type_description()

std::string qpp::exception::NotBipartite::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.47 qpp::exception::NotImplemented Class Reference


Code not yet implemented.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotImplemented:



Collaboration diagram for qpp::exception::NotImplemented:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.47.1 Detailed Description

Code not yet implemented.

7.47.2 Member Function Documentation

7.47.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.47.2.2 type_description()

std::string qpp::exception::NotImplemented::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.48 qpp::exception::NotQubitCvector Class Reference


Column vector is not 2 x 1 exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception::NotQubitCvector:$



Collaboration diagram for qpp::exception::NotQubitCvector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.48.1 Detailed Description

Column vector is not 2 x 1 exception.

Eigen::Matrix is not 2 x 1

7.48.2 Member Function Documentation

7.48.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred
-------	--

7.48.2.2 type_description()

std::string qpp::exception::NotQubitCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.49 qpp::exception::NotQubitMatrix Class Reference


Matrix is not 2 x 2 exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception::NotQubitMatrix:$



 $Collaboration\ diagram\ for\ qpp::exception::NotQubitMatrix:$



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.49.1 Detailed Description

Matrix is not 2 x 2 exception.

Eigen::Matrix is not 2 x 2

7.49.2 Member Function Documentation

7.49.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.49.2.2 type_description()

std::string qpp::exception::NotQubitMatrix::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.50 qpp::exception::NotQubitRvector Class Reference


Row vector is not 1 x 2 exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception::NotQubitRvector:$



 $Collaboration\ diagram\ for\ qpp::exception::NotQubitRvector:$



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.50.1 Detailed Description

Row vector is not 1 x 2 exception.

Eigen::Matrix is not 1 x 2

7.50.2 Member Function Documentation

7.50.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred
-------	--

7.50.2.2 type_description()

std::string qpp::exception::NotQubitRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


• classes/exception.h

7.51 qpp::exception::NotQubitSubsys Class Reference


Subsystems are not qubits exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception::NotQubitSubsys:$



Collaboration diagram for qpp::exception::NotQubitSubsys:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.51.1 Detailed Description

Subsystems are not qubits exception.

Subsystems are not 2-dimensional (qubits)

7.51.2 Member Function Documentation

7.51.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred
	Toxi representing where the exception eccurred

7.51.2.2 type_description()

std::string qpp::exception::NotQubitSubsys::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.52 qpp::exception::NotQubitVector Class Reference


Vector is not 2 x 1 nor 1 x 2 exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception::NotQubitVector:$



 $Collaboration\ diagram\ for\ qpp::exception::NotQubitVector:$



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.52.1 Detailed Description

Vector is not 2 x 1 nor 1 x 2 exception.

Eigen::Matrix is not 2 x 1 nor 1 x 2

7.52.2 Member Function Documentation

7.52.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.52.2.2 type_description()

std::string qpp::exception::NotQubitVector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


• classes/exception.h

7.53 qpp::exception::OutOfRange Class Reference


Argument out of range exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::OutOfRange:



Collaboration diagram for qpp::exception::OutOfRange:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.53.1 Detailed Description

Argument out of range exception.

Argument out of range

7.53.2 Member Function Documentation

7.53.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred
	Toxi representing where the exception eccurred

7.53.2.2 type_description()

std::string qpp::exception::OutOfRange::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


• classes/exception.h

7.54 qpp::exception::PermInvalid Class Reference


Invalid permutation exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermInvalid:



Collaboration diagram for qpp::exception::PermInvalid:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.54.1 Detailed Description

Invalid permutation exception.

std::vector<idx> does note represent a valid permutation

7.54.2 Member Function Documentation

7.54.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.54.2.2 type_description()

std::string qpp::exception::PermInvalid::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.55 qpp::exception::PermMismatchDims Class Reference


Permutation mismatch dimensions exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::PermMismatchDims:



Collaboration diagram for qpp::exception::PermMismatchDims:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.55.1 Detailed Description

Permutation mismatch dimensions exception.

Size of the std::vector<idx> representing the permutation is different from the size of the std::vector<idx> of dimensions

7.55.2 Member Function Documentation

7.55.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.55.2.2 type_description()

std::string qpp::exception::PermMismatchDims::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.56 qpp::QCircuit Class Reference


Quantum circuit class.

#include <classes/circuits/circuits.h>

Inheritance diagram for qpp::QCircuit:



Collaboration diagram for qpp::QCircuit:



Classes

struct GateStep

One step consisting only of gates/operators in the circuit.

· class iterator

Quantum circuit bound-checking (safe) iterator.

struct MeasureStep

One step consisting only of measurements in the circuit.

Public Types

enum GateType {

GateType::NONE, GateType::SINGLE, GateType::TWO, GateType::THREE,
GateType::CUSTOM, GateType::FAN, GateType::SINGLE_CTRL_SINGLE_TARGET, GateType::SINGLE_CTRL_MULTIPLE_
GateType::MULTIPLE_CTRL_SINGLE_TARGET, GateType::MULTIPLE_CTRL_MULTIPLE_TARGET,
GateType::CUSTOM_CTRL, GateType::SINGLE_cCTRL_SINGLE_TARGET,
GateType::SINGLE_cCTRL_MULTIPLE_TARGET, GateType::MULTIPLE_cCTRL_SINGLE_TARGET,
GateType::MULTIPLE_cCTRL_MULTIPLE_TARGET, GateType::CUSTOM_cCTRL}

Type of gate being executed in a gate step.

 enum MeasureType { MeasureType::NONE, MeasureType::MEASURE_Z, MeasureType::MEASURE_V, MeasureType::MEASURE V MANY }

Type of measurement being executed in a measurement step.

• enum StepType { StepType::NONE, StepType::GATE, StepType::MEASUREMENT, StepType::NOP }

Types of each step in the quantum circuit.

• using const iterator = iterator

both iterators are const_iterators

Public Member Functions

iterator begin ()

Iterator to the first element.

· const iterator begin () const noexcept

Constant iterator to the first element.

const_iterator cbegin () const noexcept

Constant iterator to the first element.

· iterator end ()

Iterator to the next to the last element.

const_iterator end () const noexcept

Constant iterator to the next to the last element.

· const iterator cend () const noexcept

Constant iterator to the next to the last element.

QCircuit (idx nq, idx nc=0, idx d=2, std::string name="")

Constructs a quantum circuit.

virtual ~QCircuit ()=default

Default virtual destructor.

• idx get_nq () const noexcept

Total number of qudits in the circuit.

• idx get_nc () const noexcept

Total number of classical dits in the circuit.

• idx get d () const noexcept

Dimension of the comprising qudits.

• std::string get_name () const

Quantum circuit name.

· idx get measured (idx i) const

Check whether qudit i was already measured.

std::vector< idx > get_measured () const

Vector of already measured gudit indexes.

std::vector< idx > get_non_measured () const

Vector of non-measured qudit indexes.

• idx get_gate_count (const std::string &name="") const

Quantum circuit gate count.

idx get_gate_depth (const std::string &name="") const

Quantum circuit gate depth.

idx get measurement count () const noexcept

Quantum circuit total measurement count.

• idx get measurement count (const std::string &name) const

Quantum circuit measurement count.

idx get_step_count () const noexcept

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

• idx get_nop_count () const

No-op count.

QCircuit & gate (const cmat &U, idx i, std::string name="")

Applies the single qudit gate U on single qudit i.

QCircuit & gate (const cmat &U, idx i, idx j, std::string name="")

Applies the two qudit gate U on qudits i and j.

• QCircuit & gate (const cmat &U, idx i, idx j, idx k, std::string name="")

Applies the three qudit gate U on qudits i, j and k.

QCircuit & gate_fan (const cmat &U, const std::vector < idx > &target, std::string name="")

Applies the single qudit gate U on every qudit listed in target.

QCircuit & gate_fan (const cmat &U, const std::initializer_list< idx > &target, std::string name="")

Applies the single qudit gate U on every qudit listed in target.

QCircuit & gate_fan (const cmat &U, std::string name="")

Applies the single qudit gate U on every remaining non-measured qudit.

QCircuit & gate_custom (const cmat &U, const std::vector < idx > &target, std::string name="")

Jointly applies the custom multiple qudit gate U on the qudit indexes specified by target.

QCircuit & QFT (const std::vector < idx > &target, bool swap=true)

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & QFT (const std::initializer list< idx > &target, bool swap=true)

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & QFT (bool swap=true)

Applies the quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

QCircuit & TFQ (const std::vector < idx > &target, bool swap QPP_UNUSED_=true)

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & TFQ (const std::initializer_list< idx > &target, bool swap=true)

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & TFQ (bool swap=true)

Applies the inverse quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

• QCircuit & CTRL (const cmat &U, idx ctrl, idx target, std::string name="")

Applies the single qudit controlled gate U with control qudit ctrl and target qudit target.

QCircuit & CTRL (const cmat &U, idx ctrl, const std::vector< idx > &target, std::string name="")

Applies the single qudit controlled gate U with control qudit ctrl on every qudit listed in target.

QCircuit & CTRL (const cmat &U, const std::vector < idx > &ctrl, idx target, std::string name="")

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on the target qudit target.

QCircuit & CTRL (const cmat &U, const std::vector < idx > &ctrl, const std::vector < idx > &target, std::string name="")

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on every qudit listed in target.

QCircuit & CTRL_custom (const cmat &U, const std::vector< idx > &ctrl, const std::vector< idx > &target, std::string name="")

Jointly applies the custom multiple-qudit controlled gate U with multiple control qudits listed in ctrl on the qudit indexes specified by target.

QCircuit & cCTRL (const cmat &U, idx ctrl_dit, idx target, std::string name="")

Applies the single qubit controlled gate U with classical control dit ctrl and target qudit target.

• QCircuit & cCTRL (const cmat &U, idx ctrl dit, const std::vector < idx > &target, std::string name=""")

Applies the single qudit controlled gate U with classical control dit ctrl on every qudit listed in target.

QCircuit & cCTRL (const cmat &U, const std::vector < idx > &ctrl dits, idx target, std::string name="")

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on the target qudit target.

QCircuit & cCTRL (const cmat &U, const std::vector< idx > &ctrl_dits, const std::vector< idx > &target, std::string name="")

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on every qudit listed in target.

QCircuit & cCTRL_custom (const cmat &U, const std::vector< idx > &ctrl_dits, const std::vector< idx > &target, std::string name="")

Jointly applies the custom multiple-qudit controlled gate U with multiple classical control dits listed in ctrl on the qudit indexes specified by target.

QCircuit & measureZ (idx target, idx c reg, std::string name="")

Measurement of single qudit in the computational basis (Z-basis)

QCircuit & measureV (const cmat &V, idx target, idx c_reg, std::string name=""")

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

QCircuit & measureV (const cmat &V, const std::vector< idx > &target, idx c reg, std::string name="")

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

• QCircuit & nop ()

No operation (no-op)

std::string to_JSON (bool enclosed_in_curly_brackets=true) const override

qpp::IJOSN::to_JSON() override

Private Member Functions

```
    void add_hash_ (const cmat &U, std::size_t hashU)
        Adds matrix to the hash table.
    const std::vector< MeasureStep > & get_measurements_ () const noexcept
        Vector of qpp::QCircuit::MeasureStep.
    const std::vector< GateStep > & get_gates_ () const noexcept
        Vector of qpp::QCircuit::GateStep.
    const std::unordered_map< std::size_t, cmat > & get_cmat_hash_tbl_ () const noexcept
        Hash table with the matrices used in the circuit.
    std::ostream & display (std::ostream &os) const override
```

Private Attributes

qpp::IDisplay::display() override

```
    const idx nq

     number of qudits

    const idx nc_

     number of classical "dits"

    const idx d

     qudit dimension
· std::string name_
     optional circuit name

    std::vector< bool > measured

     keeps track of the measured qudits
• std::unordered map< std::size t, cmat > cmat hash tbl {}
std::unordered_map< std::string, idx > count_{{}}
     keeps track of the gate counts
std::unordered_map< std::string, idx > measurement_count_{}{}
     keeps track of the measurement counts
std::vector< GateStep > gates_{}{}
     gates
std::vector< MeasureStep > measurements_{}{}
     measurements
std::vector< StepType > step_types_{}
     type of each step
```

Friends

```
    class QEngine
    std::ostream & operator << (std::ostream &os, const GateType &gate_type)
        Extraction operator overload for qpp::QCircuit::GateType enum class.</li>
    std::ostream & operator << (std::ostream &os, const GateStep &gate_step)
        Extraction operator overload for qpp::QCircuit::GateStep class.</li>
    std::ostream & operator << (std::ostream &os, const MeasureType &measure_type)
        Extraction operator overload for qpp::QCircuit::MeasureType enum class.</li>
    std::ostream & operator << (std::ostream &os, const MeasureStep &measure_step)</li>
```

Extraction operator overload for qpp::QCircuit::MeasureStep class.

7.56.1 Detailed Description

Quantum circuit class.

See also

qpp::QEngine

7.56.2 Member Typedef Documentation

```
7.56.2.1 const_iterator
```

```
using qpp::QCircuit::const_iterator = iterator
```

both iterators are const_iterators

7.56.3 Member Enumeration Documentation

7.56.3.1 GateType

```
enum qpp::QCircuit::GateType [strong]
```

Type of gate being executed in a gate step.

Enumerator

Enumerator	
NONE	represents no gate
SINGLE	unitary gate on a single qudit
TWO	unitary gate on 2 qudits
THREE	unitary gate on 3 qudits
CUSTOM	custom gate on multiple qudits
FAN	same unitary gate on multiple qudits
SINGLE_CTRL_SINGLE_TARGET	controlled 1 qudit unitary gate with one control and one target
SINGLE_CTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with one control and multiple targets
MULTIPLE_CTRL_SINGLE_TARGET	controlled 1 qudit unitary gate with multiple controls and single target
MULTIPLE_CTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with multiple controls and multiple targets
CUSTOM_CTRL	custom controlled gate with multiple controls and multiple targets
SINGLE_cCTRL_SINGLE_TARGET	controlled 1 qudit unitary gate with one classical control and one target
SINGLE_cCTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with one classical control and multiple targets
General Colly TIPLE CCTRL_SINGLE_TARGET	controlled 1 qudit unitary gate with multiple classical controls and single target
MULTIPLE_cCTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with multiple classical controls and multiple targets
-	

7.56.3.2 MeasureType

```
enum qpp::QCircuit::MeasureType [strong]
```

Type of measurement being executed in a measurement step.

Enumerator

NONE	represents no measurement
MEASURE_Z	Z measurement of single qudit.
MEASURE_V	measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix $\it V$
MEASURE_V_MANY	measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix $\it V$

7.56.3.3 StepType

```
enum qpp::QCircuit::StepType [strong]
```

Types of each step in the quantum circuit.

Enumerator

NONE	represents no step
GATE	quantum gate(s)
MEASUREMENT	measurement
NOP	no-op

7.56.4 Constructor & Destructor Documentation

7.56.4.1 QCircuit()

```
qpp::QCircuit::QCircuit (
    idx nq,
    idx nc = 0,
    idx d = 2,
    std::string name = "" ) [inline], [explicit]
```

Constructs a quantum circuit.

Note

The measurement results can only be stored in the classical dits of which number is specified by *nc*

Parameters

nq	Number of qbits
nc	Number of classical dits (optional)
d	Subsystem dimensions (optional, default is qubit, i.e. $d = 2$)
name	Circuit name (optional)

7.56.4.2 ~QCircuit()

```
virtual qpp::QCircuit::~QCircuit ( ) [virtual], [default]
```

Default virtual destructor.

7.56.5 Member Function Documentation

7.56.5.1 add_hash_()

Adds matrix to the hash table.

Note

Throws if a hash collision is detected., i.e., if two different matrices have the same hash

Parameters

U	Complex matrix
hashU	Hash value of U

7.56.5.2 begin() [1/2]

```
iterator qpp::QCircuit::begin ( ) [inline]
```

Iterator to the first element.

Returns

Iterator to the first element

```
7.56.5.3 begin() [2/2]
```

```
const_iterator qpp::QCircuit::begin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

7.56.5.4 cbegin()

```
const_iterator qpp::QCircuit::cbegin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

7.56.5.5 cCTRL() [1/4]

Applies the single qubit controlled gate *U* with classical control dit *ctrl* and target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.56.5.6 cCTRL() [2/4]
```

Applies the single qudit controlled gate *U* with classical control dit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the
	classical control dits
name	Optional gate name

Returns

Reference to the current instance

```
7.56.5.7 cCTRL() [3/4]
```

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.56.5.8 cCTRL() [4/4]
```

```
const std::vector< idx > & ctrl_dits,
const std::vector< idx > & target,
std::string name = "" ) [inline]
```

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the
	classical control dits
name	Optional gate name

Returns

Reference to the current instance

7.56.5.9 cCTRL_custom()

Jointly applies the custom multiple-qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the qudit indexes specified by *target*.

Parameters

U	Multiple-qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit indexes where the gate U is applied depending on the values of the classical control dits
name	Optional gate name

Returns

Reference to the current instance

7.56.5.10 cend()

```
const_iterator qpp::QCircuit::cend ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

Returns

Constant iterator to the next to the last element

Applies the single qudit controlled gate *U* with control qudit *ctrl* and target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.56.5.12 CTRL() [2/4]
```

Applies the single qudit controlled gate *U* with control qudit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.56.5.14 CTRL() [4/4]
```

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

7.56.5.15 CTRL_custom()

Jointly applies the custom multiple-qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the qudit indexes specified by *target*.

Parameters

U	Multiple-qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes where the gate U is applied depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

7.56.5.16 display()

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the quantum circuit

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.56.5.17 end() [1/2]
```

```
iterator qpp::QCircuit::end ( ) [inline]
```

Iterator to the next to the last element.

Returns

Iterator to the next to the last element

```
7.56.5.18 end() [2/2]
const_iterator qpp::QCircuit::end ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

Returns

Constant iterator to the next to the last element

Applies the single qudit gate *U* on single qudit *i*.

Parameters

U	Single qudit quantum gate
i	Qudit index
name	Optional gate name

Returns

Reference to the current instance

```
idx i,
idx j,
std::string name = "" ) [inline]
```

Applies the two qudit gate U on qudits i and j.

Parameters

U	Two qudit quantum gate
i	Qudit index
j	Qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.56.5.21 gate() [3/3]
```

Applies the three qudit gate U on qudits i, j and k.

Parameters

U	Three qudit quantum gate
i	Qudit index
j	Qudit index
k	Qudit index
name	Optional gate name

Returns

Reference to the current instance

7.56.5.22 gate_custom()

Jointly applies the custom multiple qudit gate *U* on the qudit indexes specified by *target*.

Parameters

U	Multiple qudit quantum gate
target	Subsystem indexes where the gate U is applied
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit gate *U* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
target	Target qudit indexes; the gate <i>U</i> is applied on every one of them
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit gate *U* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
target	Target qudit indexes; the gate U is applied on every one of them
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit gate U on every remaining non-measured qudit.

Parameters

U	Single qudit quantum gate	
name	Optional gate name	

Returns

Reference to the current instance

7.56.5.26 get_cmat_hash_tbl_()

```
const std::unordered_map<std::size_t, cmat>& qpp::QCircuit::get_cmat_hash_tbl_ ( ) const
[inline], [private], [noexcept]
```

Hash table with the matrices used in the circuit.

Returns

Hash table with the matrices used in the circuit

```
7.56.5.27 get_d()
```

```
idx qpp::QCircuit::get_d ( ) const [inline], [noexcept]
```

Dimension of the comprising qudits.

Returns

Qudit dimension

```
7.56.5.28 get_gate_count()
```

Quantum circuit gate count.

Note

If name is empty (default), returns the total gate count of the circuit

Parameters

```
name Gate name (optional)
```

Returns

Gate count

7.56.5.29 get_gate_depth()

Quantum circuit gate depth.

Note

If name is empty (default), returns the total gate depth of the circuit

Parameters

name Gate name (optional)

Returns

Gate depth

```
7.56.5.30 get_gates_()
```

```
const std::vector<GateStep>& qpp::QCircuit::get_gates_ ( ) const [inline], [private], [noexcept]
Vector of qpp::QCircuit::GateStep.
```

Total of approximation

Returns

Vector of qpp::QCircuit::GateStep

```
7.56.5.31 get_measured() [1/2]
```

Check whether qudit *i* was already measured.

Parameters

```
i Qudit index
```

Returns

True if qudit i was already measured, false othwewise

```
7.56.5.32 get_measured() [2/2]
std::vector<idx> qpp::QCircuit::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

```
7.56.5.33 get_measurement_count() [1/2]
```

```
idx qpp::QCircuit::get_measurement_count ( ) const [inline], [noexcept]
```

Quantum circuit total measurement count.

Returns

Total measurement count

```
7.56.5.34 get_measurement_count() [2/2]
```

Quantum circuit measurement count.

Do					
Pа	ra	m	eı	re.	rs

name Measurement name	
-----------------------	--

Returns

Measurement count

7.56.5.35 get_measurements_()

```
const std::vector<MeasureStep>& qpp::QCircuit::get_measurements_ ( ) const [inline], [private],
[noexcept]
```

Vector of qpp::QCircuit::MeasureStep.

Returns

Vector of qpp::QCircuit::MeasureStep

7.56.5.36 get_name()

```
std::string qpp::QCircuit::get_name ( ) const [inline]
```

Quantum circuit name.

Returns

Quantum circuit name

7.56.5.37 get_nc()

```
idx qpp::QCircuit::get_nc ( ) const [inline], [noexcept]
```

Total number of classical dits in the circuit.

Returns

Total number of classical dits

```
7.56.5.38 get_non_measured()
std::vector<idx> qpp::QCircuit::get_non_measured ( ) const [inline]
Vector of non-measured qudit indexes.
Returns
     Vector of non-measured qudit indexes
7.56.5.39 get_nop_count()
idx qpp::QCircuit::get_nop_count ( ) const [inline]
No-op count.
Returns
     No-op count
7.56.5.40 get_nq()
idx qpp::QCircuit::get_nq ( ) const [inline], [noexcept]
Total number of qudits in the circuit.
Returns
     Total number of qudits
7.56.5.41 get_step_count()
idx qpp::QCircuit::get_step_count ( ) const [inline], [noexcept]
Quantum circuit total steps count, i.e. the sum of gate count and measurement count.
Returns
     Total (gates + measurements) count
7.56.5.42 measureV() [1/2]
```

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

std::string name = "") [inline]

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V	
target	Qudit index	
c_reg	Classical register where the value of the measurement is stored	
name	Optional measurement name	

Returns

Reference to the current instance

7.56.5.43 measureV() [2/2]

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V
target	Target qudit indexes that are jointly measured
c_reg	Classical register where the value of the measurement is stored
name	Optional measurement name

Returns

Reference to the current instance

7.56.5.44 measureZ()

Measurement of single qudit in the computational basis (Z-basis)

Parameters

target	Qudit index
c_reg	Classical register where the value of the measurement is being stored
name	Optional measurement name, default is "Measure Z"

Returns

Reference to the current instance

```
7.56.5.45 nop()
```

```
QCircuit& qpp::QCircuit::nop ( ) [inline]
```

No operation (no-op)

Note

If the underlying step is executed on a noisy engine, then noise acts before it

Returns

Reference to the current instance

```
7.56.5.46 QFT() [1/3]
```

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the quantum Fourier transform is applied	
swap	Swaps the qubits at the end (true by default)	

Returns

Reference to the current instance

```
7.56.5.47 QFT() [2/3]
```

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

Applies the quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

Parameters

swap	Swaps the qubits at the end (true by default)
------	---

Returns

Reference to the current instance

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the inverse quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

bool swap = true) [inline]

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the inverse quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

Applies the inverse quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

Parameters

swap	Swaps the qubits at the end (true by default)
------	---

Returns

Reference to the current instance

```
7.56.5.52 to_JSON()
```

qpp::IJOSN::to_JSON() override

Displays the quantum circuit in JSON format

Parameters

enclosed_in_curly_brackets If true, encloses the result in curly brackets	enclosed in curly brackets	If true, encloses the result in curly brackets
---	----------------------------	--

Returns

String containing the JSON representation of the quantum circuit

Implements qpp::IJSON.

7.56.6 Friends And Related Function Documentation

Extraction operator overload for qpp::QCircuit::GateType enum class.

Parameters

os	Output stream
gate_type	qpp::QCircuit::GateType enum class

Returns

Output stream

```
7.56.6.2 operator << [2/4]
```

Extraction operator overload for qpp::QCircuit::GateStep class.

Parameters

os	Output stream
gate_step	qpp::QCircuit::GateStep class

Returns

Output stream

Extraction operator overload for qpp::QCircuit::MeasureType enum class.

Parameters

os	Output stream
measure_type	qpp::QCircuit::MeasureType enum class

Returns

Output stream

const MeasureStep & measure_step) [friend]

Extraction operator overload for qpp::QCircuit::MeasureStep class.

Parameters

os	Output stream
measure_step	qpp::QCircuit::MeasureStep enum class

Returns

Output stream

7.56.6.5 QEngine

```
friend class QEngine [friend]
```

7.56.7 Member Data Documentation

```
7.56.7.1 cmat_hash_tbl_
std::unordered_map<std::size_t, cmat> qpp::QCircuit::cmat_hash_tbl_ {} [private]
hash table with the matrices used in the circuit, with [Key = idx, Value = cmat]
7.56.7.2 count_
std::unordered_map<std::string, idx> qpp::QCircuit::count_ {} [private]
keeps track of the gate counts
7.56.7.3 d_
const idx qpp::QCircuit::d_ [private]
qudit dimension
7.56.7.4 gates_
std::vector<GateStep> qpp::QCircuit::gates_ {} [private]
gates
7.56.7.5 measured_
std::vector<bool> qpp::QCircuit::measured_ [private]
keeps track of the measured qudits
7.56.7.6 measurement_count_
std::unordered_map<std::string, idx> qpp::QCircuit::measurement_count_ {} [private]
keeps track of the measurement counts
```

```
7.56.7.7 measurements_
std::vector<MeasureStep> qpp::QCircuit::measurements_ {} [private]
measurements
7.56.7.8 name_
std::string qpp::QCircuit::name_ [private]
optional circuit name
7.56.7.9 nc_
const idx qpp::QCircuit::nc_ [private]
number of classical "dits"
7.56.7.10 nq_
const idx qpp::QCircuit::nq_ [private]
number of qudits
7.56.7.11 step_types_
std::vector<StepType> qpp::QCircuit::step_types_ {} [private]
type of each step
The documentation for this class was generated from the following file:
```

Generated by Doxygen


· classes/circuits/circuits.h

7.57 qpp::QEngine Class Reference


Quantum circuit engine, executes qpp::QCircuit.

#include <classes/circuits/engines.h>

Inheritance diagram for qpp::QEngine:



Collaboration diagram for qpp::QEngine:



Public Member Functions

• QEngine (const QCircuit &qc)

Constructs a quantum engine out of a quantum circuit.

QEngine (const QEngine &)=default

Default copy constructor.

• QEngine & operator= (const QEngine &)=default

Default copy assignment operator.

• QEngine (QCircuit &&)=delete

Disables rvalue QCircuit.

virtual ~QEngine ()=default

Default virtual destructor.

· ket get psi () const

Underlying quantum state.

std::vector< idx > get_dits () const

Vector with the values of the underlying classical dits.

• idx get_dit (idx i) const

Value of the classical dit at position i.

std::vector< double > get_probs () const

Vector of underlying measurement outcome probabilities.

bool get_measured (idx i) const

Check whether qudit i was already measured.

std::vector< idx > get_measured () const

Vector of already measured qudit indexes.

std::vector< idx > get non measured () const

Vector of non-measured gudit indexes.

· const QCircuit & get_circuit () const noexcept

Quantum circuit.

QEngine & set_dit (idx i, idx value)

Sets the classical dit at position i.

QEngine & set_psi (const ket &psi)

Sets the underlying quantum state to psi.

• void reset ()

Resets the engine.

virtual void execute (const QCircuit::iterator::value type &elem)

Executes one step in the quantum circuit.

virtual void execute (const QCircuit::iterator &it)

Executes one step in the quantum circuit.

std::string to_JSON (bool enclosed_in_curly_brackets=true) const override

qpp::IJOSN::to_JSON() override

Protected Member Functions

void set_measured_ (idx i)

Marks qudit i as measured then re-label accordingly the remaining non-measured qudits.

std::vector< idx > get_relative_pos_ (std::vector< idx > v)

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

Protected Attributes

const QCircuit * qc

pointer to constant quantum circuit

ket psi_

state vector

std::vector< idx > dits

classical dits

std::vector< double > probs_

measurement probabilities

std::vector< idx > subsys_

relabel them after measurements

Private Member Functions

std::ostream & display (std::ostream &os) const override
 qpp::IDisplay::display() override

7.57.1 Detailed Description

Quantum circuit engine, executes qpp::QCircuit.

See also

qpp::QCircuit

7.57.2 Constructor & Destructor Documentation

Constructs a quantum engine out of a quantum circuit.

Note

The quantum circuit must be an Ivalue

See also

```
qpp::QEngine(QCircuit&&)
```

Note

The initial underlying quantum state is set to $|0\rangle^{\otimes n}$

Parameters

```
qc Quantum circuit
```

7.57.2.2 QEngine() [2/3]

Default copy constructor.

Disables rvalue QCircuit.

```
7.57.2.4 ~QEngine()
```

```
virtual qpp::QEngine::~QEngine ( ) [virtual], [default]
```

Default virtual destructor.

7.57.3 Member Function Documentation

7.57.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the state of the engine

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

Executes one step in the quantum circuit.

Parameters

```
elem Step to be executed
```

Reimplemented in qpp::QNoisyEngine < NoiseModel >.

Executes one step in the quantum circuit.

Parameters

```
it Iterator to the step to be executed
```

Reimplemented in qpp::QNoisyEngine < NoiseModel >.

```
7.57.3.4 get_circuit()
```

```
const QCircuit& qpp::QEngine::get_circuit ( ) const [inline], [noexcept]
```

Quantum circuit.

Returns

Underlying quantum circuit

```
7.57.3.5 get_dit()
```

```
idx qpp::QEngine::get_dit (
          idx i ) const [inline]
```

Value of the classical dit at position i.

Parameters

i Classical dit index

Returns

Value of the classical dit at position i

7.57.3.6 get_dits()

```
std::vector<idx> qpp::QEngine::get_dits ( ) const [inline]
```

Vector with the values of the underlying classical dits.

Returns

Vector of underlying classical dits

7.57.3.7 get_measured() [1/2]

```
bool qpp::QEngine::get_measured (
          idx i ) const [inline]
```

Check whether qudit *i* was already measured.

Parameters

i Qudit index

Returns

True if qudit i was already measured, false othwewise

7.57.3.8 get_measured() [2/2]

```
std::vector<idx> qpp::QEngine::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

7.57.3.9 get_non_measured()

```
std::vector<idx> qpp::QEngine::get_non_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

Returns

Vector of non-measured gudit indexes

```
7.57.3.10 get_probs()
```

```
std::vector<double> qpp::QEngine::get_probs ( ) const [inline]
```

Vector of underlying measurement outcome probabilities.

Those should be interpreted as conditional probabilities based on the temporal order of the measurements, i.e. if we measure qubit 0, then measure qubit 1, and finally qubit 2, the resulting vector of outcome probabilities probs[2] should be interpreted as the conditional probability of qubit 2 having the outcome it had given that qubit 1 and qubit 0 had their given outcomes, respectively. As an example, if we measure the qubit 0 followed by the qubit 1 of a maximally entangled state $(|00\rangle + |11\rangle)/\sqrt{2}$, then the vector of outcome probabilities will be [0.5, 1].

Note

The probability vector has the same length as the vector of classical dits. If the measurement result is stored at the index c_reg , then the outcome probability is automatically stored at the same index c_reg in the probability vector.

Returns

Vector of underlying measurement outcome probabilities

```
7.57.3.11 get_psi()
```

```
ket qpp::QEngine::get_psi ( ) const [inline]
```

Underlying quantum state.

Returns

Underlying quantum state

7.57.3.12 get_relative_pos_()

Giving a vector *V* of non-measured qudits, get their relative position with respect to the measured qudits.

Parameters



Returns

Vector of qudit indexes

7.57.3.13 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

7.57.3.14 reset()

```
void qpp::QEngine::reset ( ) [inline]
```

Resets the engine.

Re-initializes everything to zero and sets the initial state to $|0\rangle^{\otimes n}$

7.57.3.15 set_dit()

Sets the classical dit at position i.

Parameters

i	Classical dit index
value	Classical dit value

Returns

Reference to the current instance

7.57.3.16 set_measured_()

Marks qudit *i* as measured then re-label accordingly the remaining non-measured qudits.

Parameters

```
i Qudit index
```

7.57.3.17 set_psi()

Sets the underlying quantum state to psi.

Note

The order is lexicographical with respect to the remaining non-measured qudits

Parameters

```
psi State vector
```

Returns

Reference to the current instance

7.57.3.18 to_JSON()

qpp::IJOSN::to_JSON() override

Displays the state of the engine in JSON format

Parameters

enclosed_in_curly_brackets	If true, encloses the result in curly brackets
----------------------------	--

Returns

String containing the JSON representation of the state of the engine

Implements qpp::IJSON.

7.57.4 Member Data Documentation

```
7.57.4.1 dits
std::vector<idx> qpp::QEngine::dits_ [protected]
classical dits
7.57.4.2 probs_
std::vector<double> qpp::QEngine::probs_ [protected]
measurement probabilities
7.57.4.3 psi_
ket qpp::QEngine::psi_ [protected]
state vector
7.57.4.4 qc_
const QCircuit* qpp::QEngine::qc_ [protected]
```

pointer to constant quantum circuit

7.57.4.5 subsys_

```
std::vector<idx> qpp::QEngine::subsys_ [protected]
```

relabel them after measurements

keeps track of the measured subsystems,

The documentation for this class was generated from the following file:


• classes/circuits/engines.h

7.58 qpp::QNoisyEngine < NoiseModel > Class Template Reference


Noisy quantum circuit engine, executes qpp::QCircuit.

#include <classes/circuits/engines.h>

Inheritance diagram for qpp::QNoisyEngine < NoiseModel >:



 $\label{local_continuous_continu$



Public Member Functions

QNoisyEngine (const QCircuit &qc, const NoiseModel &noise)

Constructs a noisy quantum engine out of a quantum circuit.

void execute (const QCircuit::iterator::value_type &elem) override

Executes one step in the quantum circuit.

· void execute (const QCircuit::iterator &it) override

Executes one step in the noisy quantum circuit.

std::vector< std::vector< idx > > get_noise_results () const

Vector of noise results obtained before every step in the circuit.

Private Attributes

• const NoiseModel noise_

quantum noise model

std::vector< std::vector< idx >> noise_results_

noise results

Additional Inherited Members

7.58.1 Detailed Description

```
template<typename NoiseModel> class qpp::QNoisyEngine< NoiseModel>
```

Noisy quantum circuit engine, executes qpp::QCircuit.

See also

qpp::QCircuit, qpp::NoiseBase

Assumes an uncorrelated noise model that is applied to each non-measured qubit before every step in the logical circuit

Template Parameters

```
NoiseModel Quantum noise model, should be derived from qpp::NoiseBase
```

7.58.2 Constructor & Destructor Documentation

7.58.2.1 QNoisyEngine()

```
template<trypename NoiseModel >
qpp::QNoisyEngine< NoiseModel >::QNoisyEngine (
```

```
const QCircuit & qc,
const NoiseModel & noise ) [inline], [explicit]
```

Constructs a noisy quantum engine out of a quantum circuit.

Parameters

qc	Quantum circuit
noise	Quantum noise model

7.58.3 Member Function Documentation

```
7.58.3.1 execute() [1/2]
```

Executes one step in the quantum circuit.

Parameters

elem	Step to be executed
------	---------------------

Reimplemented from qpp::QEngine.

```
7.58.3.2 execute() [2/2]
```

Executes one step in the noisy quantum circuit.

Parameters

```
it Iterator to the step to be executed
```

Reimplemented from qpp::QEngine.

7.58.3.3 get_noise_results()

```
template<typename NoiseModel >
std::vector<std::vector<idx> > qpp::QNoisyEngine< NoiseModel >::get_noise_results ( ) const
[inline]
```

Vector of noise results obtained before every step in the circuit.

The first vector contains the noise measurement results obtained before applying the first step in the circuit, and so on, ordered by non-measured qudits. That is, the first element in the vector corresponding to noise obtained before a given step in the circuit represents the noise result obtained on the first non-measured qudit etc.

Returns

Vector of noise results

7.58.4 Member Data Documentation

```
7.58.4.1 noise
```

```
template<typename NoiseModel >
const NoiseModel qpp::QNoisyEngine< NoiseModel >::noise_ [private]
```

quantum noise model

7.58.4.2 noise_results_

```
template<typename NoiseModel >
std::vector<std::vector<idx> > qpp::QNoisyEngine< NoiseModel >::noise_results_ [private]
```

noise results

The documentation for this class was generated from the following file:


classes/circuits/engines.h

7.59 qpp::QubitAmplitudeDampingNoise Class Reference


Qubit amplitude damping noise, as described in Nielsen and Chuang.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitAmplitudeDampingNoise:



Collaboration diagram for qpp::QubitAmplitudeDampingNoise:



Public Member Functions

• QubitAmplitudeDampingNoise (double gamma)

Qubit amplitude damping noise constructor.

Additional Inherited Members

7.59.1 Detailed Description

Qubit amplitude damping noise, as described in Nielsen and Chuang.

7.59.2 Constructor & Destructor Documentation

7.59.2.1 QubitAmplitudeDampingNoise()

Qubit amplitude damping noise constructor.

Parameters

ga	amma	Amplitude damping coefficient
----	------	-------------------------------

The documentation for this class was generated from the following file:


classes/noise.h

7.60 qpp::QubitBitFlipNoise Class Reference


Qubit bit flip noise.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitBitFlipNoise:



Collaboration diagram for qpp::QubitBitFlipNoise:



Public Member Functions

QubitBitFlipNoise (double p)
 Qubit bit flip noise constructor.

Additional Inherited Members

7.60.1 Detailed Description

Qubit bit flip noise.

7.60.2 Constructor & Destructor Documentation

7.60.2.1 QubitBitFlipNoise()

```
\label{eq:qpp::QubitBitFlipNoise} $$ \operatorname{qpp}::\operatorname{QubitBitFlipNoise} ($$ \operatorname{double} p ) [inline], [explicit] $$
```

Qubit bit flip noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.61 qpp::QubitBitPhaseFlipNoise Class Reference


Qubit bit-phase flip (dephasing) noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitBitPhaseFlipNoise:



Collaboration diagram for qpp::QubitBitPhaseFlipNoise:



Public Member Functions

QubitBitPhaseFlipNoise (double p)
 Qubit bit-phase flip noise constructor.

Additional Inherited Members

7.61.1 Detailed Description

Qubit bit-phase flip (dephasing) noise.

7.61.2 Constructor & Destructor Documentation

7.61.2.1 QubitBitPhaseFlipNoise()

```
\label{eq:qpp::QubitBitPhaseFlipNoise::QubitBitPhaseFlipNoise (} \\ \text{double } p \text{ ) } \quad \text{[inline], [explicit]}
```

Qubit bit-phase flip noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


classes/noise.h

7.62 qpp::QubitDepolarizingNoise Class Reference


Qubit depolarizing noise.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitDepolarizingNoise:



Collaboration diagram for qpp::QubitDepolarizingNoise:



Public Member Functions

QubitDepolarizingNoise (double p)
 Qubit depolarizing noise constructor.

Additional Inherited Members

7.62.1 Detailed Description

Qubit depolarizing noise.

7.62.2 Constructor & Destructor Documentation

7.62.2.1 QubitDepolarizingNoise()

```
\label{eq:qpp::QubitDepolarizingNoise::QubitDepolarizingNoise (} $$ double $p$ ) [inline], [explicit]
```

Qubit depolarizing noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.63 qpp::QubitPhaseDampingNoise Class Reference


Qubit phase damping noise, as described in Nielsen and Chuang.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitPhaseDampingNoise:



Collaboration diagram for qpp::QubitPhaseDampingNoise:



Public Member Functions

QubitPhaseDampingNoise (double lambda)
 Qubit phase damping noise constructor.

Additional Inherited Members

7.63.1 Detailed Description

Qubit phase damping noise, as described in Nielsen and Chuang.

7.63.2 Constructor & Destructor Documentation

7.63.2.1 QubitPhaseDampingNoise()

Qubit phase damping noise constructor.

Parameters

lambda Phase damping coefficient	
----------------------------------	--

The documentation for this class was generated from the following file:


· classes/noise.h

7.64 qpp::QubitPhaseFlipNoise Class Reference


Qubit phase flip (dephasing) noise.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitPhaseFlipNoise:



Collaboration diagram for qpp::QubitPhaseFlipNoise:



Public Member Functions

• QubitPhaseFlipNoise (double p)

Qubit phase flip (dephasing) noise constructor.

Additional Inherited Members

7.64.1 Detailed Description

Qubit phase flip (dephasing) noise.

7.64.2 Constructor & Destructor Documentation

7.64.2.1 QubitPhaseFlipNoise()

Qubit phase flip (dephasing) noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


• classes/noise.h

7.65 qpp::exception::QuditAlreadyMeasured Class Reference


Qudit was already measured exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::QuditAlreadyMeasured:



Collaboration diagram for qpp::exception::QuditAlreadyMeasured:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.65.1 Detailed Description

Qudit was already measured exception.

The qudit was already measured and cannot be measured again

7.65.2 Member Function Documentation

7.65.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred	
-------	--	--

7.65.2.2 type_description()

std::string qpp::exception::QuditAlreadyMeasured::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.66 qpp::QuditDepolarizingNoise Class Reference


Qudit depolarizing noise.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QuditDepolarizingNoise:



Collaboration diagram for qpp::QuditDepolarizingNoise:



Public Member Functions

QuditDepolarizingNoise (double p, idx d)
 Qudit depolarizing noise constructor.

Private Member Functions

• std::vector< cmat > fill_Ks_ (idx d) const

Fills the Kraus operator vector.

std::vector< double > fill_probs_ (double p, idx d) const
 Fills the probability vector.

Additional Inherited Members

7.66.1 Detailed Description

Qudit depolarizing noise.

7.66.2 Constructor & Destructor Documentation

7.66.2.1 QuditDepolarizingNoise()

```
qpp::QuditDepolarizingNoise::QuditDepolarizingNoise ( double p,  idx \ d \ ) \ \ [inline], \ [explicit]
```

Qudit depolarizing noise constructor.

Parameters

р	Noise probability
d	Qudit dimension

7.66.3 Member Function Documentation

Fills the Kraus operator vector.

Parameters

```
d Qudit dimension
```

Returns

Vector of Kraus operators representing the depolarizing noise

```
7.66.3.2 fill_probs_()
```

Fills the probability vector.

Parameters

р	Probability
d	Qudit dimension

Returns

Probability vector

The documentation for this class was generated from the following file:


• classes/noise.h

7.67 qpp::RandomDevices Class Reference


Singleton class that manages the source of randomness in the library.

#include <classes/random_devices.h>

Inheritance diagram for qpp::RandomDevices:



Collaboration diagram for qpp::RandomDevices:



Public Member Functions

• std::mt19937 & get_prng ()

Returns a reference to the internal PRNG object.

• std::istream & load (std::istream &is)

Loads the state of the PRNG from an input stream.

• std::ostream & save (std::ostream &os) const

Saves the state of the PRNG to an output stream.

Private Member Functions

• RandomDevices ()

Initializes and seeds the random number generators.

∼RandomDevices ()=default

Default destructor.

Private Attributes

 std::random_device rd_ used to seed std::mt19937 prng_

std::mt19937 prng_

Mersenne twister random number generator.

Friends

class internal::Singleton < RandomDevices >

Additional Inherited Members

7.67.1 Detailed Description

Singleton class that manages the source of randomness in the library.

Warning

This class DOES NOT seed the standard C number generator used by Eigen::Matrix::Random(), since it is not thread safe. Do not use Eigen::Matrix::Random() or functions that depend on the C style random number engine, but use qpp::rand() instead!

7.67.2 Constructor & Destructor Documentation

7.67.2.1 RandomDevices()

```
qpp::RandomDevices::RandomDevices ( ) [inline], [private]
```

Initializes and seeds the random number generators.

7.67.2.2 ~RandomDevices()

```
\verb"qpp::RandomDevices::$\sim$RandomDevices ( ) [private], [default]
```

Default destructor.

7.67.3 Member Function Documentation

```
7.67.3.1 get_prng()
```

```
std::mt19937& qpp::RandomDevices::get_prng ( ) [inline]
```

Returns a reference to the internal PRNG object.

Returns

Reference to the internal PRNG object

7.67.3.2 load()

```
std::istream& qpp::RandomDevices::load (  \texttt{std::istream \& } is \ ) \quad [inline]
```

Loads the state of the PRNG from an input stream.

Parameters

```
is Input stream
```

Returns

The input stream

7.67.3.3 save()

Saves the state of the PRNG to an output stream.

Parameters

os Output stream

Returns

The output stream

7.67.4 Friends And Related Function Documentation

```
7.67.4.1 internal::Singleton < Random Devices >
```

```
friend class internal::Singleton< RandomDevices > [friend]
```

7.67.5 Member Data Documentation

```
7.67.5.1 prng_
```

```
std::mt19937 qpp::RandomDevices::prng_ [private]
```

Mersenne twister random number generator.

```
7.67.5.2 rd_
```

```
std::random_device qpp::RandomDevices::rd_ [private]
```

used to seed std::mt19937 prng_

The documentation for this class was generated from the following file:

• classes/random_devices.h

7.68 qpp::internal::Singleton < T > Class Template Reference

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

```
#include <internal/classes/singleton.h>
```

Static Public Member Functions

- static T & get_instance () noexcept(std::is_nothrow_constructible < T >::value)
- static T & get thread local instance () noexcept(std::is nothrow constructible < T >::value)

Protected Member Functions

- Singleton () noexcept=default
- Singleton (const Singleton &)=delete
- Singleton & operator= (const Singleton &)=delete
- virtual ∼Singleton ()=default

7.68.1 Detailed Description

```
\label{template} \begin{tabular}{ll} template < typename T > \\ class & qpp::internal::Singleton < T > \\ \end{tabular}
```

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

To implement a singleton, derive your class from qpp::internal::Singleton, make qpp::internal::Singleton a friend of your class, then declare the constructor and destructor of your class as private. To get an instance, use the static member function qpp::internal::Singleton::get_instance() (qpp::internal::Singleton::get_thread_local_instance()), which returns a reference (thread_local_reference) to your newly created singleton (thread-safe in C++11).

Example:

See also

Code of qpp::Codes, qpp::Gates, qpp::Init, qpp::RandomDevices, qpp::States or qpp.h for real world examples of usage.

7.68.2 Constructor & Destructor Documentation

```
7.68.2.1 Singleton() [1/2]
template<typename T>
qpp::internal::Singleton < T >::Singleton ( ) [protected], [default], [noexcept]
7.68.2.2 Singleton() [2/2]
template<typename T>
qpp::internal::Singleton < T >::Singleton (
            const Singleton< T > \& ) [protected], [delete]
7.68.2.3 ∼Singleton()
template<typename T>
virtual qpp::internal::Singleton< T >::~Singleton ( ) [protected], [virtual], [default]
7.68.3 Member Function Documentation
7.68.3.1 get_instance()
template<typename T>
\texttt{static T\& qpp::internal::Singleton} < \texttt{T} > :: \texttt{get\_instance ()} \quad \texttt{[inline], [static], [noexcept]}
7.68.3.2 get_thread_local_instance()
template<typename T>
static T& qpp::internal::Singleton< T >::get_thread_local_instance ( ) [inline], [static],
[noexcept]
7.68.3.3 operator=()
template<typename T>
Singleton& qpp::internal::Singleton< T >::operator= (
              const Singleton< T > \& ) [protected], [delete]
```

The documentation for this class was generated from the following file:


• internal/classes/singleton.h

7.69 qpp::exception::SizeMismatch Class Reference


Size mismatch exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SizeMismatch:



Collaboration diagram for qpp::exception::SizeMismatch:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.69.1 Detailed Description

Size mismatch exception.

Sizes do not match

7.69.2 Member Function Documentation

7.69.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.69.2.2 type_description()

```
std::string qpp::exception::SizeMismatch::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

classes/exception.h

7.70 qpp::NoiseType::StateDependent Class Reference

Template tag, used whenever the noise is state-dependent.

#include <classes/noise.h>

7.70.1 Detailed Description

Template tag, used whenever the noise is state-dependent.

The documentation for this class was generated from the following file:

· classes/noise.h

7.71 qpp::NoiseType::StateIndependent Class Reference

Template tag, used whenever the noise is state-independent.

#include <classes/noise.h>

7.71.1 Detailed Description

Template tag, used whenever the noise is state-independent.

The documentation for this class was generated from the following file:


classes/noise.h

7.72 qpp::States Class Reference


const Singleton class that implements most commonly used states

#include <classes/states.h>

Inheritance diagram for qpp::States:



Collaboration diagram for qpp::States:



Public Member Functions

• ket mes (idx d=2) const

Maximally entangled state of 2 qudits.

• ket zero (idx n, idx d=2) const

Zero state of n qudits.

• ket one (idx n, idx d=2) const

One state of n qudits.

• ket jn (idx j, idx n, idx d=2) const

 $|j\rangle^{\otimes n}$ state of n qudits

• ket plus (idx n) const

Plus state of n qubits.

• ket minus (idx n) const

Minus state of n qubits.

Public Attributes

```
    ket x0 {ket::Zero(2)}
```

Pauli Sigma-X 0-eigenstate |+>

ket x1 {ket::Zero(2)}

Pauli Sigma-X 1-eigenstate |->

ket y0 {ket::Zero(2)}

Pauli Sigma-Y 0-eigenstate |y+>

ket y1 {ket::Zero(2)}

Pauli Sigma-Y 1-eigenstate | y->

ket z0 {ket::Zero(2)}

Pauli Sigma-Z 0-eigenstate |0>

ket z1 {ket::Zero(2)}

Pauli Sigma-Z 1-eigenstate | 1>

cmat px0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

• cmat px1 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.

```
    cmat py0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 0-eigenstate |y+\rangle < y+|.

    cmat py1 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.

    cmat pz0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
• cmat pz1 {cmat::Zero(2, 2)}
      Projector onto the Pauli Sigma-Z 1-eigenstate | 1><1|.
ket b00 {ket::Zero(4)}
      Bell-00 state, as described in Nielsen and Chuang.

    ket b01 {ket::Zero(4)}

      Bell-01 state, as described in Nielsen and Chuang.

    ket b10 {ket::Zero(4)}

      Bell-10 state, as described in Nielsen and Chuang.
ket b11 {ket::Zero(4)}
      Bell-11 state, as described in Nielsen and Chuang.

    cmat pb00 {cmat::Zero(4, 4)}

      Projector onto the Bell-00 state.

    cmat pb01 {cmat::Zero(4, 4)}

      Projector onto the Bell-01 state.

    cmat pb10 {cmat::Zero(4, 4)}

      Projector onto the Bell-10 state.

    cmat pb11 {cmat::Zero(4, 4)}

      Projector onto the Bell-11 state.
ket GHZ {ket::Zero(8)}
      GHZ state.

    ket W {ket::Zero(8)}

      W state.
```

Private Member Functions

- States ()
- ∼States ()=default

Default destructor.

cmat pGHZ {cmat::Zero(8, 8)}
 Projector onto the GHZ state.

cmat pW {cmat::Zero(8, 8)}
 Projector onto the W state.

Friends

class internal::Singleton < const States >

Additional Inherited Members

7.72.1 Detailed Description

const Singleton class that implements most commonly used states

7.72.2 Constructor & Destructor Documentation

```
7.72.2.1 States()

qpp::States::States ( ) [inline], [private]

Initialize the states

7.72.2.2 ~States()

qpp::States::~States ( ) [private], [default]
```

7.72.3 Member Function Documentation

7.72.3.1 jn()

Default destructor.

 $|j\rangle^{\otimes n}$ state of *n* qudits

Parameters

j	Non-negative integer
n	Non-negative integer
d	Subsystem dimensions

Returns

 $|j\rangle^{\otimes n}$ state of *n* qudits

7.72.3.2 mes()

```
ket qpp::States::mes (
idx d = 2 ) const [inline]
```

Maximally entangled state of 2 qudits.

Parameters

d Subsystem dimensions

Returns

Maximally entangled state $\frac{1}{\sqrt{d}} \sum_{j=0}^{d-1} |jj\rangle$ of 2 qudits

7.72.3.3 minus()

```
ket qpp::States::minus (
          idx n ) const [inline]
```

Minus state of n qubits.

Parameters

n Non-negative integer

Returns

Minus state $|-\rangle^{\otimes n}$ of n qubits

7.72.3.4 one()

```
ket qpp::States::one (
        idx n,
        idx d = 2 ) const [inline]
```

One state of *n* qudits.

Parameters

n	Non-negative integer
d	Subsystem dimensions

Returns

One state $|1\rangle^{\otimes n}$ of n qudits

7.72.3.5 plus()

```
ket qpp::States::plus (
         idx n ) const [inline]
```

Plus state of *n* qubits.

Parameters

```
n Non-negative integer
```

Returns

Plus state $|+\rangle^{\otimes n}$ of n qubits

7.72.3.6 zero()

```
ket qpp::States::zero (
         idx n,
         idx d = 2 ) const [inline]
```

Zero state of *n* qudits.

Parameters

n	Non-negative integer
d	Subsystem dimensions

Returns

Zero state $|0\rangle^{\otimes n}$ of n qudits

7.72.4 Friends And Related Function Documentation

```
7.72.4.1 internal::Singleton < const States >
```

```
friend class internal::Singleton< const States > [friend]
```

7.72.5 Member Data Documentation

```
7.72.5.1 b00
```

```
ket qpp::States::b00 {ket::Zero(4)}
```

Bell-00 state, as described in Nielsen and Chuang.

```
7.72.5.2 b01
```

```
ket qpp::States::b01 {ket::Zero(4)}
```

Bell-01 state, as described in Nielsen and Chuang.

```
7.72.5.3 b10
```

```
ket qpp::States::b10 {ket::Zero(4)}
```

Bell-10 state, as described in Nielsen and Chuang.

7.72.5.4 b11

```
ket qpp::States::b11 {ket::Zero(4)}
```

Bell-11 state, as described in Nielsen and Chuang.

7.72.5.5 GHZ

```
ket qpp::States::GHZ {ket::Zero(8)}
```

GHZ state.

7.72.5.6 pb00

```
cmat qpp::States::pb00 {cmat::Zero(4, 4)}
```

Projector onto the Bell-00 state.

```
7.72.5.7 pb01
cmat qpp::States::pb01 {cmat::Zero(4, 4)}
Projector onto the Bell-01 state.
7.72.5.8 pb10
cmat qpp::States::pb10 {cmat::Zero(4, 4)}
Projector onto the Bell-10 state.
7.72.5.9 pb11
cmat qpp::States::pb11 {cmat::Zero(4, 4)}
Projector onto the Bell-11 state.
7.72.5.10 pGHZ
cmat qpp::States::pGHZ {cmat::Zero(8, 8)}
Projector onto the GHZ state.
7.72.5.11 pW
cmat qpp::States::pW {cmat::Zero(8, 8)}
Projector onto the W state.
```

Generated by Doxygen

cmat qpp::States::px0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

7.72.5.12 px0

```
7.72.5.13 px1
cmat qpp::States::px1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.
7.72.5.14 py0
cmat qpp::States::py0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 0-eigenstate |y+>< y+|.
7.72.5.15 py1
cmat qpp::States::py1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.
7.72.5.16 pz0
cmat qpp::States::pz0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
7.72.5.17 pz1
cmat qpp::States::pz1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 1-eigenstate |1><1|.
7.72.5.18 W
ket qpp::States::W {ket::Zero(8)}
W state.
```

```
7.72.5.19 x0
ket qpp::States::x0 {ket::Zero(2)}
Pauli Sigma-X 0-eigenstate |+>
7.72.5.20 x1
ket qpp::States::x1 {ket::Zero(2)}
Pauli Sigma-X 1-eigenstate |->
7.72.5.21 y0
ket qpp::States::y0 {ket::Zero(2)}
Pauli Sigma-Y 0-eigenstate |y+>
7.72.5.22 y1
ket qpp::States::y1 {ket::Zero(2)}
Pauli Sigma-Y 1-eigenstate |y->
7.72.5.23 z0
ket qpp::States::z0 {ket::Zero(2)}
Pauli Sigma-Z 0-eigenstate |0>
7.72.5.24 z1
ket qpp::States::z1 {ket::Zero(2)}
Pauli Sigma-Z 1-eigenstate |1>
The documentation for this class was generated from the following file:
```

Generated by Doxygen


classes/states.h

7.73 qpp::exception::SubsysMismatchDims Class Reference


Subsystems mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SubsysMismatchDims:



Collaboration diagram for qpp::exception::SubsysMismatchDims:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.73.1 Detailed Description

Subsystems mismatch dimensions exception.

std::vector<idx> of subsystem labels has duplicates, or has entries that are larger than the size of the std← ::vector<idx> of dimensions

7.73.2 Member Function Documentation

7.73.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred	

7.73.2.2 type_description()

```
std::string qpp::exception::SubsysMismatchDims::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.74 qpp::Timer < T, CLOCK_T > Class Template Reference


Chronometer.

#include <classes/timer.h>

Inheritance diagram for qpp::Timer< T, CLOCK_T >:



Collaboration diagram for qpp::Timer < T, CLOCK_T >:



Public Member Functions

· Timer () noexcept

Constructs an instance with the current time as the starting point.

• void tic () noexcept

Resets the chronometer.

• const Timer & toc () noexcept

Stops the chronometer.

• double tics () const noexcept

Time passed in the duration specified by T.

• template<typename U = T>

U get_duration () const noexcept

Duration specified by U.

• Timer (const Timer &)=default

Default copy constructor.

• Timer (Timer &&)=default

Default move constructor.

• Timer & operator= (const Timer &)=default

Default copy assignment operator.

• Timer & operator= (Timer &&)=default

Default move assignment operator.

virtual ∼Timer ()=default

Default virtual destructor.

Protected Attributes

- CLOCK_T::time_point start_
- CLOCK_T::time_point end_

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display() override*

7.74.1 Detailed Description

```
template < typename\ T = std::chrono::duration < double >, typename\ CLOCK\_T = std::chrono::steady\_clock > class\ qpp::Timer < T,\ CLOCK\_T >
```

Chronometer.

Template Parameters

T	Tics duration, default is std::chrono::duration <double, 1="">, i.e. seconds in double precision</double,>
CLOCK← T	Clock's type, default is std::chrono::steady_clock, not affected by wall clock changes during runtime

7.74.2 Constructor & Destructor Documentation

```
7.74.2.1 Timer() [1/3]
```

```
\label{template} $$ \ensuremath{\texttt{template}}$ $$ \ensuremath{\texttt{typename T = std::chrono::steady}}$ $$ $$ \ensuremath{\texttt{clock}}$ $$ \ensuremath{\texttt{clock}}$ $$ $$ \ensuremath{\texttt{qpp::Timer}}$ $$ \ensuremath{\texttt{T, CLOCK\_T >::Timer}}$ $$ ( ) $$ [inline], [noexcept] $$
```

Constructs an instance with the current time as the starting point.

7.74.2.2 Timer() [2/3]

Default copy constructor.

7.74.2.3 Timer() [3/3]

Default move constructor.

7.74.2.4 \sim Timer()

```
\label{template} $$ \ensuremath{\sf template}$ $$ \ensurem
```

Default virtual destructor.

7.74.3 Member Function Documentation

7.74.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream the number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc().

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.74.3.2 get_duration()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady 
_clock>
template<typename U = T>
U qpp::Timer< T, CLOCK_T >::get_duration ( ) const [inline], [noexcept]
```

Duration specified by U.

Template Parameters

U Duration, default is T, which defaults to std::chrono::duration<double, 1>, i.e. seconds in double precision

Returns

Duration that passed between the instantiation/reset and invocation of qpp::Timer::toc()

7.74.3.3 operator=() [1/2]

Default copy assignment operator.

7.74.3.4 operator=() [2/2]

Default move assignment operator.

7.74.3.5 tic()

```
 \begin{tabular}{ll} template < type name T = std::chrono::duration < double>, type name CLOCK_T = std::chrono::steady & clock> \\ void qpp::Timer < T, CLOCK_T >::tic ( ) [inline], [noexcept] \\ \end{tabular}
```

Resets the chronometer.

Resets the starting/ending point to the current time

7.74.3.6 tics()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
double qpp::Timer< T, CLOCK_T >::tics ( ) const [inline], [noexcept]
```

Time passed in the duration specified by T.

Returns

Number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc()

7.74.3.7 toc()

```
 \begin{tabular}{ll} template < type name $T = std::chrono::steady \leftarrow \_clock > \\ const $Timer\& $qpp::Timer < T, $CLOCK_T > ::toc ( ) [inline], [noexcept] \end{tabular}
```

Stops the chronometer.

Set the current time as the ending point

Returns

Reference to the current instance

7.74.4 Member Data Documentation

7.74.4.1 end

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady←
   _clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::end_ [protected]
```

7.74.4.2 start_

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::start_ [protected]
```

The documentation for this class was generated from the following file:


· classes/timer.h

7.75 qpp::exception::TypeMismatch Class Reference

Type mismatch exception.


```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::TypeMismatch:



360 Class Documentation

Collaboration diagram for qpp::exception::TypeMismatch:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.75.1 Detailed Description

Type mismatch exception.

Scalar types do not match

7.75.2 Member Function Documentation

7.75.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.75.2.2 type_description()

std::string qpp::exception::TypeMismatch::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.76 qpp::exception::UndefinedType Class Reference

Not defined for this type exception.


```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::UndefinedType:



362 Class Documentation

Collaboration diagram for qpp::exception::UndefinedType:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.76.1 Detailed Description

Not defined for this type exception.

Templated specialization is not defined for this type

7.76.2 Member Function Documentation

7.76.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.76.2.2 type_description()

std::string qpp::exception::UndefinedType::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.77 qpp::exception::Unknown Class Reference

Unknown exception.


#include <classes/exception.h>

Inheritance diagram for qpp::exception::Unknown:



364 Class Documentation

Collaboration diagram for qpp::exception::Unknown:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.77.1 Detailed Description

Unknown exception.

Thrown when no other exception is suitable (not recommended, it is better to define another suitable exception type)

7.77.2 Member Function Documentation

7.77.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred
--

7.77.2.2 type_description()

std::string qpp::exception::Unknown::type_description () const [inline], [override], [virtual]
Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

· classes/exception.h


7.78 qpp::QCircuit::iterator::value_type_ Class Reference

Value type class for qpp::QCircuit::iterator.

Inheritance diagram for qpp::QCircuit::iterator::value_type_:



 $Collaboration\ diagram\ for\ qpp:: QCircuit:: iterator:: value_type_:$



366 Class Documentation

Public Member Functions

```
    value_type_ (const QCircuit *value_type_qc)
        Default value_type_ constructor.
    value_type_ (const value_type_ &)=default
        Default copy constructor.
    value_type_ & operator= (const value_type_ &)=default
        Default copy assignment operator.
```

Public Attributes

```
    const QCircuit * value_type_qc_
        < non-owning pointer to the grand-parent const quantum circuit</li>
    StepType type_{StepType::NONE}
        step type
    idx ip_{static_cast<idx>(-1)}
        instruction pointer
    std::vector< GateStep >::const_iterator gates_ip_{gates instruction pointer}
    std::vector< MeasureStep >::const_iterator measurements_ip_{measurements instruction pointer}
```

Private Member Functions

7.78.1 Detailed Description

Value type class for qpp::QCircuit::iterator.

7.78.2 Constructor & Destructor Documentation

Parameters

value_type_qc	Pointer to constant quantum circuit
---------------	-------------------------------------

Default copy constructor.

7.78.3 Member Function Documentation

7.78.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream the textual representation of the iterator de-referenced element

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.78.3.2 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

7.78.4 Member Data Documentation

368 Class Documentation

```
7.78.4.1 gates_ip_
std::vector<GateStep>::const_iterator qpp::QCircuit::iterator::value_type_::gates_ip_ {}
gates instruction pointer
7.78.4.2 ip_
idx qpp::QCircuit::iterator::value_type_::ip_ {static_cast<idx>(-1)}
instruction pointer
7.78.4.3 measurements_ip_
\verb|std::vector<| \texttt{MeasureStep}>::const_iterator | qpp::QCircuit::iterator::value_type_::measurements\_{\leftarrow}| to the const_iterator | to the const_itera
measurements instruction pointer
7.78.4.4 type_
StepType qpp::QCircuit::iterator::value_type_::type_ {StepType::NONE}
step type
7.78.4.5 value_type_qc_
const QCircuit* qpp::QCircuit::iterator::value_type_::value_type_qc_
 < non-owning pointer to the grand-parent const quantum circuit
The documentation for this class was generated from the following file:
```


classes/circuits/circuits.h

7.79 qpp::exception::ZeroSize Class Reference


Object has zero size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::ZeroSize:



Collaboration diagram for qpp::exception::ZeroSize:



370 Class Documentation

Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.79.1 Detailed Description

Object has zero size exception.

Zero sized object, e.g. empty Eigen::Matrix or std::vector with no elements

7.79.2 Member Function Documentation

7.79.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.79.2.2 type_description()

std::string qpp::exception::ZeroSize::type_description () const [inline], [override], [virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h


Chapter 8

File Documentation

8.1 classes/circuits/circuits.h File Reference

Qudit quantum circuits.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::QCircuit

Quantum circuit class.

• struct qpp::QCircuit::GateStep

One step consisting only of gates/operators in the circuit.

• struct qpp::QCircuit::MeasureStep

One step consisting only of measurements in the circuit.

· class qpp::QCircuit::iterator

Quantum circuit bound-checking (safe) iterator.

• class qpp::QCircuit::iterator::value_type_

Value type class for qpp::QCircuit::iterator.

Namespaces

• qpp

Quantum++ main namespace.


8.1.1 Detailed Description

Qudit quantum circuits.

8.2 classes/circuits/engines.h File Reference

Qudit quantum engines.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::QEngine

Quantum circuit engine, executes qpp::QCircuit.

class qpp::QNoisyEngine < NoiseModel >

Noisy quantum circuit engine, executes qpp::QCircuit.

Namespaces

• qpp

Quantum++ main namespace.


8.2.1 Detailed Description

Qudit quantum engines.

8.3 classes/codes.h File Reference

Quantum error correcting codes.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::Codes

const Singleton class that defines quantum error correcting codes

Namespaces

• qpp

Quantum++ main namespace.

8.3.1 Detailed Description

Quantum error correcting codes.

8.4 classes/exception.h File Reference

Exceptions.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::exception::Exception

Base class for generating Quantum++ custom exceptions.

class qpp::exception::Unknown

Unknown exception.

class qpp::exception::ZeroSize

Object has zero size exception.

class gpp::exception::MatrixNotSquare

Matrix is not square exception.

· class qpp::exception::MatrixNotCvector

Matrix is not a column vector exception.

class qpp::exception::MatrixNotRvector

Matrix is not a row vector exception.

class qpp::exception::MatrixNotVector

Matrix is not a vector exception.

class qpp::exception::MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

• class qpp::exception::MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

class qpp::exception::MatrixNotSquareNorVector

Matrix is not square nor vector exception.

class qpp::exception::MatrixMismatchSubsys

Matrix mismatch subsystems exception.

· class qpp::exception::DimsInvalid

Invalid dimension(s) exception.

· class qpp::exception::DimsNotEqual

Dimensions not equal exception.

class qpp::exception::DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

· class qpp::exception::DimsMismatchCvector

Dimension(s) mismatch column vector size exception.

class qpp::exception::DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

class qpp::exception::DimsMismatchVector

Dimension(s) mismatch vector size exception.

class qpp::exception::SubsysMismatchDims

Subsystems mismatch dimensions exception.

• class qpp::exception::PermInvalid

Invalid permutation exception.

· class qpp::exception::PermMismatchDims

Permutation mismatch dimensions exception.

class qpp::exception::NotQubitMatrix

Matrix is not 2 x 2 exception.

· class qpp::exception::NotQubitCvector

Column vector is not 2 x 1 exception.

class qpp::exception::NotQubitRvector

Row vector is not 1 x 2 exception.

class qpp::exception::NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

class qpp::exception::NotQubitSubsys

Subsystems are not qubits exception.

· class qpp::exception::NotBipartite

Not bi-partite exception.

· class qpp::exception::NoCodeword

Codeword does not exist exception.

class qpp::exception::OutOfRange

Argument out of range exception.

class qpp::exception::TypeMismatch

Type mismatch exception.

· class qpp::exception::SizeMismatch

Size mismatch exception.

class qpp::exception::UndefinedType

Not defined for this type exception.

• class qpp::exception::QuditAlreadyMeasured

Qudit was already measured exception.

class qpp::exception::Duplicates

System (e.g. std::vector) has duplicates exception.

class qpp::exception::CustomException

Custom exception.

· class qpp::exception::NotImplemented

Code not yet implemented.

· class qpp::exception::InvalidIterator

Invalid iterator.

Namespaces

• qpp

Quantum++ main namespace.

• qpp::exception

Quantum++ exception hierarchy namespace.


8.4.1 Detailed Description

Exceptions.

8.5 classes/gates.h File Reference

Quantum gates.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::Gates

const Singleton class that implements most commonly used gates

Namespaces

• qpp

Quantum++ main namespace.

8.5.1 Detailed Description

Quantum gates.

8.6 classes/idisplay.h File Reference

Display interface via the non-virtual interface (NVI) and very basic JSON serialization support interface.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

· class qpp::IJSON

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

Namespaces

• qpp

Quantum++ main namespace.


8.6.1 Detailed Description

Display interface via the non-virtual interface (NVI) and very basic JSON serialization support interface.

8.7 classes/init.h File Reference

Initialization.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::Init

const Singleton class that performs additional initializations/cleanups

Namespaces

• qpp

Quantum++ main namespace.


8.7.1 Detailed Description

Initialization.

8.8 classes/noise.h File Reference

Noise models.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::NoiseType

Contains template tags used to specify the noise type.

class qpp::NoiseBase< T >

Base class for all noise models, derive your particular noise model.

• class qpp::QubitDepolarizingNoise

Qubit depolarizing noise.

• class qpp::QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

• class qpp::QubitBitFlipNoise

Qubit bit flip noise.

· class qpp::QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

• class qpp::QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

• class qpp::QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

· class qpp::QuditDepolarizingNoise

Qudit depolarizing noise.

Namespaces

• qpp

Quantum++ main namespace.


8.8.1 Detailed Description

Noise models.

8.9 classes/random_devices.h File Reference

Random devices.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::RandomDevices

Singleton class that manages the source of randomness in the library.

Namespaces

qpp

Quantum++ main namespace.


8.9.1 Detailed Description

Random devices.

8.10 classes/reversible.h File Reference

Support for classical reversible circuits.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::Dynamic_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

class qpp::Bit_circuit

Classical reversible circuit simulator.

• class qpp::Bit_circuit::Gate_count

Gate counters.

· class qpp::Bit_circuit::Gate_depth

Gate depth.

Namespaces

• qpp

Quantum++ main namespace.


8.10.1 Detailed Description

Support for classical reversible circuits.

8.11 classes/states.h File Reference

Quantum states.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::States

const Singleton class that implements most commonly used states

Namespaces

• qpp

Quantum++ main namespace.


8.11.1 Detailed Description

Quantum states.

8.12 classes/timer.h File Reference

Timing.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::Timer < T, CLOCK_T >
 Chronometer.

Namespaces

• qpp

Quantum++ main namespace.


8.12.1 Detailed Description

Timing.

8.13 constants.h File Reference

Constants.

This graph shows which files directly or indirectly include this file:



Namespaces

- qpp
 - Quantum++ main namespace.
- qpp::literals

Functions

- constexpr cplx qpp::literals::operator"" _i (unsigned long long int x) noexcept
 - User-defined literal for complex $i = \sqrt{-1}$ (integer overload)
- constexpr cplx qpp::operator"" _i (long double x) noexcept
 - User-defined literal for complex $i = \sqrt{-1}$ (real overload)
- cplx qpp::omega (idx D)
 - D-th root of unity.

Variables

- constexpr double qpp::chop = 1e-10
 - Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.
- constexpr idx qpp::maxn = 64
 - Maximum number of allowed qubits/qudits (subsystems)
- constexpr double qpp::pi = 3.141592653589793238462643383279502884
 - π
- constexpr double qpp::ee = 2.718281828459045235360287471352662497
 - Base of natural logarithm, e.
- constexpr double qpp::infty = std::numeric_limits<double>::max()
 - Used to denote infinity in double precision.


8.13.1 Detailed Description

Constants.

8.14 entanglement.h File Reference

Entanglement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Schmidt basis on Bob side.

Functions

```
    template<typename Derived >
        dyn_col_vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector<
        idx > &dims)
```

Schmidt coefficients of the bi-partite pure state A.

```
    template<typename Derived >
        dyn_col_vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2)

    Schmidt coefficients of the bi-partite pure state A.
```

template<typename Derived >
 cmat qpp::schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
 Schmidt basis on Alice side.

template < typename Derived >
 cmat qpp::schmidtA (const Eigen::MatrixBase < Derived > &A, idx d=2)
 Schmidt basis on Alice side.

 $\begin{tabular}{ll} \begin{tabular}{ll} \bullet & template < typename Derived > \\ \begin{tabular}{ll} const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &dims) \\ \end{tabular}$

template<typename Derived >
 cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2)

Schmidt basis on Bob side.

template<typename Derived >
 std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx
 > &dims)

Schmidt probabilities of the bi-partite pure state A.

template<typename Derived >

std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)

Schmidt probabilities of the bi-partite pure state A.

• template<typename Derived >

double qpp::entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)

Entanglement of the bi-partite pure state A.

template<typename Derived >

double qpp::entanglement (const Eigen::MatrixBase< Derived > &A, idx d=2)

Entanglement of the bi-partite pure state A.

• template<typename Derived >

double qpp::gconcurrence (const Eigen::MatrixBase Derived > &A)

G-concurrence of the bi-partite pure state A.

• template<typename Derived >

double qpp::negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)

Negativity of the bi-partite mixed state A.

template < typename Derived >

double qpp::negativity (const Eigen::MatrixBase< Derived > &A, idx d=2)

Negativity of the bi-partite mixed state A.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)

Logarithmic negativity of the bi-partite mixed state A.

• template<typename Derived >

double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)

Logarithmic negativity of the bi-partite mixed state A.

• template<typename Derived >

double qpp::concurrence (const Eigen::MatrixBase Derived > &A)

Wootters concurrence of the bi-partite qubit mixed state A.


8.14.1 Detailed Description

Entanglement functions.

8.15 entropies.h File Reference

Entropy functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 double qpp::entropy (const Eigen::MatrixBase< Derived > &A)
 von-Neumann entropy of the density matrix A

double qpp::entropy (const std::vector< double > &prob)

Shannon entropy of the probability distribution prob.

• template<typename Derived >

double qpp::renyi (const Eigen::MatrixBase< Derived > &A, double alpha)

Renyi- α entropy of the density matrix A, for $\alpha \geq 0$.

double qpp::renyi (const std::vector< double > &prob, double alpha)

Renyi- α entropy of the probability distribution prob, for $\alpha \geq 0$.

• template<typename Derived >

double qpp::tsallis (const Eigen::MatrixBase< Derived > &A, double q)

Tsallis- q entropy of the density matrix A, for $q \ge 0$.

double qpp::tsallis (const std::vector< double > &prob, double q)

Tsallis- q entropy of the probability distribution prob, for $q \geq 0$.

• template<typename Derived >

double qpp::qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const std::vector< idx > &subsysB, const std::vector< idx > &dims)

Quantum mutual information between 2 subsystems of a composite system.

ullet template<typename Derived >

double qpp::qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const std::vector< idx > &subsysB, idx d=2)

Quantum mutual information between 2 subsystems of a composite system.

8.15.1 Detailed Description

Entropy functions.

8.16 experimental/experimental.h File Reference

Experimental/test functions/classes.

Namespaces

• qpp

Quantum++ main namespace.

· qpp::experimental

Experimental/test functions/classes, do not use or modify.


8.16.1 Detailed Description

Experimental/test functions/classes.

8.17 functions.h File Reference

Generic quantum computing functions.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::internal::HashEigen

Functor for hashing Eigen expressions.

• class qpp::internal::EqualEigen

Functor for comparing Eigen expressions for equality.

Namespaces

• qpp

Quantum++ main namespace.

- · qpp::literals
- · qpp::internal

Internal utility functions, do not use them directly or modify them.

Functions

```
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::transpose (const Eigen::MatrixBase< Derived > &A)
• template<typename Derived >
  dyn mat< typename Derived::Scalar > qpp::conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::adjoint (const Eigen::MatrixBase< Derived > &A)
      Adjoint.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::inverse (const Eigen::MatrixBase< Derived > &A)
      Inverse.

    template<typename Derived >

  Derived::Scalar qpp::trace (const Eigen::MatrixBase < Derived > &A)
• template<typename Derived >
  Derived::Scalar <a href="mailto:qpp::det">qpp::det</a> (const Eigen::MatrixBase</a> Derived > &A)

    template<typename Derived >

  Derived::Scalar qpp::logdet (const Eigen::MatrixBase< Derived > &A)
     Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar <a href="mailto:qpp::sum">qpp::sum</a> (const Eigen::MatrixBase< Derived > &A)
     Element-wise sum of A.
template<typename Derived >
  Derived::Scalar <a href="mailto:open:prod">open:prod</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise product of A.

    template<typename Derived >

  double <a href="mailto:qpp::norm">qpp::norm</a> (const Eigen::MatrixBase< Derived > &A)
      Frobenius norm.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::normalize (const Eigen::MatrixBase< Derived > &A)
      Normalizes state vector (column or row vector) or density matrix.
• template<typename Derived >
  std::pair< dyn_col_vect< cplx >, cmat > qpp::eig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition.
• template<typename Derived >
  dyn_col_vect< cplx > qpp::evals (const Eigen::MatrixBase< Derived > &A)
     Eigenvalues.

    template<typename Derived >

  cmat qpp::evects (const Eigen::MatrixBase< Derived > &A)
      Eigenvectors.

    template<typename Derived >

  std::pair< dyn_col_vect< double >, cmat > qpp::heig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > qpp::hevals (const Eigen::MatrixBase< Derived > &A)
      Hermitian eigenvalues.
• template<typename Derived >
  cmat qpp::hevects (const Eigen::MatrixBase< Derived > &A)
      Eigenvectors of Hermitian matrix.
```

```
• template<typename Derived >
    std::tuple< cmat, dyn_col_vect< double >, cmat > qpp::svd (const Eigen::MatrixBase< Derived > &A)
            Full singular value decomposition.

    template<typename Derived >

    dyn_col_vect< double > qpp::svals (const Eigen::MatrixBase< Derived > &A)
            Singular values.
• template<typename Derived >
    cmat qpp::svdU (const Eigen::MatrixBase< Derived > &A)
            Left singular vectors.

    template<typename Derived >

    cmat qpp::svdV (const Eigen::MatrixBase< Derived > &A)
            Right singular vectors.

    template<typename Derived >

    cmat qpp::funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
            Functional calculus f(A)

    template<typename Derived >

    cmat qpp::sqrtm (const Eigen::MatrixBase< Derived > &A)
            Matrix square root.
• template<typename Derived >
    cmat qpp::absm (const Eigen::MatrixBase< Derived > &A)
            Matrix absolute value.
template<typename Derived >
    cmat qpp::expm (const Eigen::MatrixBase< Derived > &A)
            Matrix exponential.

    template<typename Derived >

    cmat qpp::logm (const Eigen::MatrixBase< Derived > &A)
            Matrix logarithm.

    template<typename Derived >

    cmat <a href="mailto:qpp::sinm">qpp::sinm</a> (const Eigen::MatrixBase</a> Derived > &A)
            Matrix sin.
• template<typename Derived >
    cmat qpp::cosm (const Eigen::MatrixBase< Derived > &A)
            Matrix cos.
• template<typename Derived >
    cmat qpp::spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
            Matrix power.
template<typename Derived >
    dyn mat< typename Derived::Scalar > qpp::powm (const Eigen::MatrixBase< Derived > &A, idx n)
            Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

    template<typename Derived >

    double qpp::schatten (const Eigen::MatrixBase< Derived > &A, double p)
            Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
    \label{localized_dyn_mat} \textit{dyn\_mat} < \textit{OutputScalar} > \textit{qpp::cwise} \; (\textit{const Eigen::MatrixBase} < \textit{Derived} > \&A, \; \textit{OutputScalar}(*f)(\textit{const Eigen::MatrixBase} < \textit{Const Eigen::MatrixBase} < \textit{C
    typename Derived::Scalar &))
            Functor.
• template<typename T >
    dyn_mat< typename T::Scalar > qpp::kron (const T &head)
            Kronecker product.
template<typename T , typename... Args>
    dyn_mat< typename T::Scalar > qpp::kron (const T &head, const Args &... tail)
            Kronecker product.
```

```
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::kron (const std::vector< Derived > &As)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::kron (const std::initializer_list< Derived > &As)
     Kronecker product.
template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
      Kronecker power.

    template<typename T >

  dyn_mat< typename T::Scalar > qpp::dirsum (const T &head)
      Direct sum.
• template<typename T , typename... Args>
  dyn mat< typename T::Scalar > qpp::dirsum (const T &head, const Args &... tail)
      Direct sum.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::vector< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::initializer_list< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::reshape (const Eigen::MatrixBase< Derived > &A, idx rows,
  idx cols)
     Reshape.

    template < typename Derived1, typename Derived2 >

  dyn_mat< typename Derived1::Scalar > qpp::comm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
      Commutator.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > qpp::anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::prj (const Eigen::MatrixBase< Derived > &A)
     Projector.

    template<typename Derived >

  \label{lem:dyn_mat} \textit{dyn\_mat} < \textit{typename Derived::} \textit{Scalar} > \textit{qpp::} \textit{grams} \; (\textit{const std::} \textit{vector} < \textit{Derived} > \& \textit{As})
     Gram-Schmidt orthogonalization.
template<typename Derived >
  dyn mat< typename Derived::Scalar > qpp::grams (const std::initializer list< Derived > &As)
      Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::grams (const Eigen::MatrixBase< Derived > &A)
     Gram-Schmidt orthogonalization.

    std::vector< idx > qpp::n2multiidx (idx n, const std::vector< idx > &dims)

     Non-negative integer index to multi-index.

    idx qpp::multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

     Multi-index to non-negative integer index.

    ket qpp::mket (const std::vector< idx > &mask, const std::vector< idx > &dims)
```

Multi-partite qudit ket. ket qpp::mket (const std::vector< idx > &mask, idx d=2) Multi-partite qudit ket. cmat qpp::mprj (const std::vector < idx > &mask, const std::vector < idx > &dims) Projector onto multi-partite qudit ket. cmat qpp::mprj (const std::vector< idx > &mask, idx d=2) Projector onto multi-partite qudit ket. • template<typename InputIterator > std::vector< double > qpp::abssq (InputIterator first, InputIterator last) Computes the absolute values squared of an STL-like range of complex numbers. template<typename Container > std::vector< double > qpp::abssq (const Container &c, typename std::enable if< is iterable< Container >::value >::type *=nullptr) Computes the absolute values squared of an STL-like container. template<typename Derived > std::vector< double > qpp::abssq (const Eigen::MatrixBase< Derived > &A) Computes the absolute values squared of an Eigen expression. • template<typename InputIterator > std::iterator_traits < InputIterator >::value_type qpp::sum (InputIterator first, InputIterator last) Element-wise sum of an STL-like range. template<typename Container > Container::value_type qpp::sum (const Container &c, typename std::enable_if< is_iterable< Container >← ::value >::type *=nullptr) Element-wise sum of the elements of an STL-like container. template<typename InputIterator > std::iterator_traits< InputIterator >::value_type qpp::prod (InputIterator first, InputIterator last) Element-wise product of an STL-like range. template<typename Container > Container::value type qpp::prod (const Container &c, typename std::enable if < is iterable < Container >← ::value >::type *=nullptr) Element-wise product of the elements of an STL-like container. template<typename Derived > dyn_col_vect< typename Derived::Scalar > qpp::rho2pure (const Eigen::MatrixBase< Derived > &A) Finds the pure state representation of a matrix proportional to a projector onto a pure state. std::vector< idx > qpp::complement (std::vector< idx > subsys, idx n) Constructs the complement of a subsystem vector. template<typename Derived > std::vector< double > qpp::rho2bloch (const Eigen::MatrixBase< Derived > &A) Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A. cmat qpp::bloch2rho (const std::vector< double > &r) Computes the density matrix corresponding to the 3-dimensional real Bloch vector r. • template<char... Bits> ket qpp::literals::operator"" _ket () Multi-partite qubit ket user-defined literal. • template<char... Bits> bra qpp::literals::operator"" _bra () Multi-partite qubit bra user-defined literal. • template<char... Bits> cmat qpp::literals::operator"" _prj () Multi-partite qubit projector user-defined literal. template < class T > void qpp::internal::hash combine (std::size t &seed, const T &v) template<typename Derived > std::size_t qpp::hash_eigen (const Eigen::MatrixBase< Derived > &A, std::size_t seed=0)

Computes the hash of en Eigen matrix/vector/expression.


8.17.1 Detailed Description

Generic quantum computing functions.

8.18 input output.h File Reference

Input/output functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 internal::IOManipEigen qpp::disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
 Eigen expression ostream manipulator.

internal::IOManipEigen qpp::disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

• template<typename InputIterator >

internal::IOManipRange< InputIterator > qpp::disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")

Range ostream manipulator.

• template<typename Container >

internal::IOManipRange< typename Container::const_iterator > qpp::disp (const Container &c, const std⇔ ::string &separator, const std::string &start="[", const std::string &end="]", typename std::enable_if< is_⇔ iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

• template<typename PointerType >

internal::IOManipPointer< PointerType > qpp::disp (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")

C-style pointer ostream manipulator.

• template<typename Derived >

void qpp::save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.


8.18.1 Detailed Description

Input/output functions.

8.19 instruments.h File Reference

Measurement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)
 Generalized inner product.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

ullet template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >
 std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase
 Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

• template<typename Derived >

std::tuple < idx, std::vector < double >, std::vector < cmat > > qpp::measure (const Eigen::MatrixBase < Derived > &A, const std::vector < cmat > &Ks, const std::vector < idx > &target, const std::vector < idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template < typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > qpp::measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

• template<typename Derived >

 $std::tuple < std::vector < idx >, double, cmat > qpp::measure_seq (const Eigen::MatrixBase < Derived > \&A, std::vector < idx > target, idx d=2)$

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.


8.19.1 Detailed Description

Measurement functions.

8.20 internal/classes/iomanip.h File Reference

Input/output manipulators.

This graph shows which files directly or indirectly include this file:



Classes

- class qpp::internal::IOManipRange< InputIterator >
- class qpp::internal::IOManipPointer< PointerType >
- class qpp::internal::IOManipEigen

Namespaces

• qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


8.20.1 Detailed Description

Input/output manipulators.

8.21 internal/classes/singleton.h File Reference

Singleton pattern via CRTP.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::internal::Singleton< T >

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Namespaces

• qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


8.21.1 Detailed Description

Singleton pattern via CRTP.

8.22 internal/util.h File Reference

Internal utility functions.

This graph shows which files directly or indirectly include this file:



Classes

struct qpp::internal::Display_Impl_

Namespaces

qpp

Quantum++ main namespace.

· qpp::internal

Internal utility functions, do not use them directly or modify them.

Functions

- void qpp::internal::n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx qpp::internal::multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- $\bullet \ \ {\it template}{<} {\it typename Derived} >$

bool qpp::internal::check square mat (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

bool qpp::internal::check_vector (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_rvector (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_cvector (const Eigen::MatrixBase< Derived > &A)

template<typename T >

bool qpp::internal::check_nonzero_size (const T &x) noexcept

• template<typename T1 , typename T2 >

bool gpp::internal::check matching sizes (const T1 &lhs, const T2 &rhs) noexcept

- bool qpp::internal::check_dims (const std::vector< idx > &dims)
- ullet template<typename Derived >

bool qpp::internal::check_dims_match_mat (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_dims_match_cvect (const std::vector < idx > &dims, const Eigen::MatrixBase < Derived > &A)

• template<typename Derived >

bool qpp::internal::check_dims_match_rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- bool qpp::internal::check eq dims (const std::vector < idx > &dims, idx dim) noexcept
- bool app::internal::check no duplicates (std::vector< idx > v)
- bool qpp::internal::check_subsys_match_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)
- $\bullet \ \ \text{template}{<} \text{typename Derived} >$

bool qpp::internal::check_qubit_matrix (const Eigen::MatrixBase< Derived > &A) noexcept

• template<typename Derived >

bool qpp::internal::check_qubit_cvector (const Eigen::MatrixBase< Derived > &A) noexcept

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

 $bool\ qpp::internal::check_qubit_rvector\ (const\ Eigen::MatrixBase < Derived > \&A)\ noexcept$

 $\bullet \ \ \mathsf{template} \mathord{<} \mathsf{typename} \ \mathsf{Derived} >$

bool qpp::internal::check_qubit_vector (const Eigen::MatrixBase< Derived > &A) noexcept

- bool qpp::internal::check_perm (const std::vector< idx > &perm)
- template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::internal::kron2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::MatrixBase< Derived2 > &B)

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::internal::dirsum2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::MatrixBase< Derived2 > &B)

• template<typename T >

void qpp::internal::variadic_vector_emplace (std::vector< T > &)

- template < typename T , typename First , typename... Args >
 - void qpp::internal::variadic_vector_emplace (std::vector< T > &v, First &&first, Args &&... args)
- idx qpp::internal::get_num_subsys (idx D, idx d)
- idx qpp::internal::get_dim_subsys (idx sz, idx N)

8.22.1 Detailed Description

Internal utility functions.

8.23 MATLAB/matlab.h File Reference

Input/output interfacing with MATLAB.

```
#include "mat.h"
#include "mex.h"
```

Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< cplx > ::type
 qpp::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::

Scalar > >::type qpp::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >
 std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.


8.23.1 Detailed Description

Input/output interfacing with MATLAB.

8.24 number_theory.h File Reference

Number theory functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

std::vector< int > qpp::x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

• double qpp::contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

• bigint qpp::gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint qpp::gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint qpp::lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint qpp::lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > qpp::invperm (const std::vector< idx > &perm)

Inverse permutation.

• std::vector< idx > qpp::compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

std::vector< bigint > qpp::factors (bigint a)

Prime factor decomposition.

• bigint qpp::modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

• bigint qpp::modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple< bigint, bigint, bigint > qpp::egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint qpp::modinv (bigint a, bigint p)

Modular inverse of a mod p.

bool qpp::isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

• bigint qpp::randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

- std::vector< std::pair< int, int > > qpp::convergents (const std::vector< int > &cf)
 Convergents.
- std::vector< std::pair< int, int > > qpp::convergents (double x, idx N)
 Convergents.


8.24.1 Detailed Description

Number theory functions.

8.25 operations.h File Reference

Quantum operation functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 const std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 idx d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived >

```
cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)
```

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std \leftrightarrow ::vector< idx > &target, const std::vector< idx > &dims)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std
::vector< idx > &target, idx d=2)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat qpp::kraus2super (const std::vector< cmat > &Ks)

Superoperator matrix.

cmat qpp::kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector< cmat > qpp::choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat qpp::choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat qpp::super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

• template<typename Derived >

 $\label{lem:dyn_mat} $$ dyn_mat< typename\ Derived::Scalar > qpp::ptrace2\ (const\ Eigen::MatrixBase<\ Derived > \&A,\ const\ std $$::vector< idx > \&dims)$$

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

Partial trace.

 $\bullet \ \ {\sf template}{<} {\sf typename \ Derived}>$

dyn_mat< typename Derived::Scalar > qpp::ptrace (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Partial transpose.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2)

Partial transpose.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &perm, const std::vector< idx > &dims)

Subsystem permutation.

template<typename Derived >

 $dyn_mat < typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &perm, idx d=2)$

Subsystem permutation.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::applyQFT (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::applyTFQ (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

dyn_col_vect< typename Derived::Scalar > qpp::TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

• template<typename Derived >

 $dyn_col_vect< typename Derived::Scalar > qpp::QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)$

Qudit quantum Fourier transform.

8.25.1 Detailed Description

Quantum operation functions.

8.26 qpp.h File Reference

Quantum++ main header file, includes all other necessary headers.

```
#include <algorithm>
#include <cassert>
#include <chrono>
#include <cmath>
#include <complex>
#include <cstdlib>
#include <cstring>
#include <exception>
#include <fstream>
```

```
#include <functional>
#include <initializer list>
#include <iomanip>
#include <iterator>
#include <limits>
#include <memory>
#include <numeric>
#include <ostream>
#include <random>
#include <sstream>
#include <stdexcept>
#include <string>
#include <tuple>
#include <type_traits>
#include <unordered_map>
#include <utility>
#include <vector>
#include <Eigen/Dense>
#include <Eigen/SVD>
#include "types.h"
#include "classes/exception.h"
#include "constants.h"
#include "traits.h"
#include "classes/idisplay.h"
#include "internal/util.h"
#include "internal/classes/iomanip.h"
#include "input_output.h"
#include "internal/classes/singleton.h"
#include "classes/random_devices.h"
#include "random.h"
#include "number_theory.h"
#include "functions.h"
#include "classes/init.h"
#include "classes/codes.h"
#include "classes/gates.h"
#include "classes/states.h"
#include "statistics.h"
#include "operations.h"
#include "entropies.h"
#include "entanglement.h"
#include "classes/timer.h"
#include "instruments.h"
#include "classes/reversible.h"
#include "classes/noise.h"
#include "classes/circuits/circuits.h"
#include "classes/circuits/engines.h"
```

Namespaces

• qpp

Quantum++ main namespace.

Macros

#define QPP_UNUSED_

8.26.1 Detailed Description

Quantum++ main header file, includes all other necessary headers.

8.26.2 Macro Definition Documentation


8.26.2.1 QPP_UNUSED_

#define QPP_UNUSED_

8.27 random.h File Reference

Randomness-related functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

double qpp::rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

• bigint qpp::rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx qpp::randidx (idx a=std::numeric limits < idx >::min(), idx b=std::numeric limits < idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

template<typename Derived >

Derived qpp::rand (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double a QPP_UNUSED_=0, double b QPP_UNUSED =1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

template<>

dmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

template<>

cmat gpp::rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived qpp::randn (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double mean QPP_UNUSED_=0, double sigma QPP_UNUSED_=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

dmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

template<>

cmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

• double qpp::randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

cmat qpp::randU (idx D=2)

Generates a random unitary matrix.

• cmat qpp::randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > qpp::randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat qpp::randH (idx D=2)

Generates a random Hermitian matrix.

ket qpp::randket (idx D=2)

Generates a random normalized ket (pure state vector)

• cmat qpp::randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > qpp::randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > qpp::randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.


8.27.1 Detailed Description

Randomness-related functions.

8.28 statistics.h File Reference

Statistics functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

std::vector< double > qpp::uniform (idx N)

Uniform probability distribution vector.

std::vector< double > qpp::marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > qpp::marginalY (const dmat &probXY)

Marginal distribution.

template<typename Container >
 double qpp::avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_←
 iterable< Container >::value >::type *=nullptr)

Average.

• template<typename Container >

double qpp::cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Covariance.

template<typename Container >
 double qpp::var (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_←
 iterable< Container >::value >::type *=nullptr)

Variance.

template<typename Container >
 double qpp::sigma (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_
 iterable< Container >::value >::type *=nullptr)

Standard deviation.

template<typename Container >
 double qpp::cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if<
 is_iterable< Container >::value >::type *=nullptr)
 Correlation.


8.28.1 Detailed Description

Statistics functions.

8.29 traits.h File Reference

Type traits.

This graph shows which files directly or indirectly include this file:



Classes

- struct qpp::make_void < Ts >
 - Helper for qpp::to_void<>> alias template.
- struct qpp::is_iterable < T, typename >
 - Checks whether T is compatible with an STL-like iterable container.
- struct qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(*(std::declval < T >().end()), decltype(std::declval < T
 - Checks whether T is compatible with an STL-like iterable container, specialization for STL-like iterable containers.
- struct qpp::is_matrix_expression< Derived >
 - Checks whether the type is an Eigen matrix expression.
- struct qpp::is_complex< T >
 - Checks whether the type is a complex type.
- struct qpp::is_complex< std::complex< T >>
 - Checks whether the type is a complex number type, specialization for complex types.

Namespaces

• qpp

Quantum++ main namespace.

Typedefs

template < typename... Ts>
 using qpp::to_void = typename make_void < Ts... > ::type
 Alias template that implements the proposal for void_t.


8.29.1 Detailed Description

Type traits.

8.30 types.h File Reference

Type aliases.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Typedefs

• using qpp::idx = std::size_t

```
Non-negative integer index, make sure you use an unsigned type.
• using qpp::bigint = long long int
      Big integer.
using qpp::cplx = std::complex < double >
      Complex number in double precision.
• using qpp::ket = Eigen::VectorXcd
      Complex (double precision) dynamic Eigen column vector.
• using qpp::bra = Eigen::RowVectorXcd
      Complex (double precision) dynamic Eigen row vector.
• using qpp::cmat = Eigen::MatrixXcd
      Complex (double precision) dynamic Eigen matrix.
• using qpp::dmat = Eigen::MatrixXd
      Real (double precision) dynamic Eigen matrix.
• template<typename Scalar >
  using <a href="mailto:qpp::dyn_mat">qpp::dyn_mat</a> = Eigen::Matrix< Scalar, Eigen::Dynamic, Eigen::Dynamic >
      Dynamic Eigen matrix over the field specified by Scalar.
• template<typename Scalar >
  using qpp::dyn_col_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 >
      Dynamic Eigen column vector over the field specified by Scalar.
• template<typename Scalar >
  using qpp::dyn row vect = Eigen::Matrix < Scalar, 1, Eigen::Dynamic >
     Dynamic Eigen row vector over the field specified by Scalar.
```

8.30.1 Detailed Description

Type aliases.

8.31 /Users/vlad/qpp/README.md File Reference

Index

/Users/vlad/qpp/README.md, 408	applyTFQ
~Codes	qpp, <mark>38</mark>
qpp::Codes, 139	avg
~Dynamic_bitset	qpp, 38
qpp::Dynamic_bitset, 161	حاله المارة
~Gates	b00
qpp::Gates, 183	qpp::States, 347
	b01
~IDisplay	
qpp::IDisplay, 199	qpp::States, 348
~IJSON	b10
qpp::IJSON, 202	qpp::States, 348
~Init	b11
qpp::Init, 204	qpp::States, 348
\sim NoiseBase	bCNOT
qpp::NoiseBase, 250	qpp::Bit_circuit::Gate_depth, 178
~QCircuit	bFRED
qpp::QCircuit, 283	qpp::Bit_circuit::Gate_depth, 178
~QEngine	bNOT
qpp::QEngine, 309	qpp::Bit_circuit::Gate_depth, 179
~RandomDevices	bSWAP
qpp::RandomDevices, 335	qpp::Bit_circuit::Gate_depth, 179
~Singleton	bTOF
qpp::internal::Singleton, 339	qpp::Bit_circuit::Gate_depth, 179
\sim States	begin
qpp::States, 345	qpp::QCircuit, 283
\sim Timer	bigint
qpp::Timer, 356	qpp, 28
" 1	Bit_circuit
A_	qpp::Bit_circuit, 133
qpp::internal::IOManipEigen, 209	qpp::Bit_circuit::Gate_depth, 179
absm	bit_circuit_
qpp, 31	
	qpp::Bit_circuit::Gate_depth, 179
abssq	bloch2rho
qpp, 31, 32	qpp, 38
add_hash_	bra
qpp::QCircuit, 283	qpp, <mark>28</mark>
adjoint	btotal
qpp, 32	qpp::Bit_circuit::Gate_depth, 179
all	
qpp::Dynamic_bitset, 161	c reg
anticomm	qpp::QCircuit::MeasureStep, 245
qpp, 33	cCTRL_custom
any	qpp::QCircuit, 286
qpp::Dynamic bitset, 161	cCTRL
apply	qpp::QCircuit, 284, 285
qpp, 33–35	CNOTba
applyCTRL	qpp::Gates, 192
qpp, 36	CNOT
applyQFT	qpp::Bit_circuit, 134
app. 37	gpp::Bit circuit::Gate count, 174

qpp::Bit_circuit::Gate_depth, 179	classes/exception.h, 373
qpp::Gates, 192	classes/gates.h, 375
CTRL_custom	classes/idisplay.h, 376
qpp::QCircuit, 289	classes/init.h, 377
CTRL	classes/noise.h, 378
qpp::Gates, 184	classes/random_devices.h, 379
qpp::QCircuit, 287, 288	classes/reversible.h, 379
cbegin	classes/states.h, 380
qpp::QCircuit, 284	classes/timer.h, 381
cend	cmat
qpp::QCircuit, 286	qpp, 29
check_cvector	cmat_hash_tbl_
qpp::internal, 122	qpp::QCircuit, 303
check_dims	Codes
qpp::internal, 122	qpp::Codes, 139
check_dims_match_cvect	codeword
qpp::internal, 122	qpp::Codes, 139
check_dims_match_mat	comm
qpp::internal, 122	qpp, 40
check_dims_match_rvect	complement
qpp::internal, 122	qpp, 40
check_eq_dims	compperm
qpp::internal, 123	qpp, 41
check_matching_sizes	compute_probs_
qpp::internal, 123	qpp::NoiseBase, 251
check_no_duplicates	compute_state_
qpp::internal, 123	qpp::NoiseBase, 251
check_nonzero_size	concurrence
qpp::internal, 123	qpp, 41
check_perm	conjugate
qpp::internal, 123	qpp, 42 const iterator
check_qubit_cvector qpp::internal, 123	qpp::QCircuit, 281
check_qubit_matrix	constants.h. 382
qpp::internal, 124	contfrac2x
check qubit rvector	qpp, 42
qpp::internal, 124	convergents
check_qubit_vector	qpp, 42, 43
qpp::internal, 124	cor
check_rvector	qpp, 43
qpp::internal, 124	cosm
check_square_mat	qpp, 44
qpp::internal, 124	count
check_subsys_match_dims	qpp::Dynamic_bitset, 161
qpp::internal, 124	count
check vector	qpp::QCircuit, 304
qpp::internal, 125	COV
choi2kraus	qpp, 44
qpp, 39	cplx
choi2super	qpp, 29
qpp, 39	ctrl
chop	qpp::QCircuit::GateStep, 196
qpp, 118	CustomException
chop_	qpp::exception::CustomException, 141
qpp::internal::IOManipEigen, 209	cwise
classes/circuits/circuits.h, 371	qpp, 45
classes/circuits/engines.h, 372	CZ
classes/codes.h, 373	qpp::Gates, 192
	-11-1

d_	entropies.h, 384
qpp::NoiseBase, 254	entropy
qpp::QCircuit, 304	qpp, 52, 53
data	evals
qpp::Dynamic_bitset, 161	qpp, 53
det	evects
qpp, 45	qpp, 53
difference_type	Exception
qpp::QCircuit::iterator, 222	qpp::exception::DimsInvalid, 144
dirsum	qpp::exception::DimsMismatchCvector, 146
qpp, 46, 47	qpp::exception::DimsMismatchMatrix, 148
dirsum2	qpp::exception::DimsMismatchNeatrix, 146 qpp::exception::DimsMismatchRvector, 150
qpp::internal, 125	
	qpp::exception::DimsMismatchVector, 152
dirsumpow	qpp::exception::DimsNotEqual, 154
qpp, 47	qpp::exception::Duplicates, 157
disp	qpp::exception::Exception, 172
qpp, 48–50	qpp::exception::InvalidIterator, 206
display	qpp::exception::MatrixMismatchSubsys, 228
qpp::Dynamic_bitset, 162	qpp::exception::MatrixNotCvector, 230
qpp::IDisplay, 200	qpp::exception::MatrixNotRvector, 232
qpp::QCircuit, 289	qpp::exception::MatrixNotSquare, 234
<pre>qpp::QCircuit::iterator::value_type_, 367</pre>	<pre>qpp::exception::MatrixNotSquareNorCvector, 236</pre>
qpp::QEngine, 309	qpp::exception::MatrixNotSquareNorRvector, 238
qpp::Timer, 356	qpp::exception::MatrixNotSquareNorVector, 240
qpp::internal::IOManipEigen, 209	qpp::exception::MatrixNotVector, 242
qpp::internal::IOManipPointer, 211	qpp::exception::NoCodeword, 247
qpp::internal::IOManipRange, 214	qpp::exception::NotBipartite, 257
display_impl_	qpp::exception::NotImplemented, 259
qpp::internal::Display_Impl_, 155	qpp::exception::NotQubitCvector, 261
dits_	qpp::exception::NotQubitMatrix, 263
qpp::QEngine, 315	qpp::exception::NotQubitRvector, 265
dmat	qpp::exception::NotQubitSubsys, 267
qpp, 29	qpp::exception::NotQubitVector, 269
dyn_col_vect	qpp::exception::OutOfRange, 271
qpp, 29	qpp::exception::PermInvalid, 273
dyn mat	qpp::exception::PermMismatchDims, 275
· —	qpp::exception::QuditAlreadyMeasured, 330
qpp, 29	
dyn_row_vect	qpp::exception::SizeMismatch, 341
qpp, 30	qpp::exception::SubsysMismatchDims, 353
Dynamic_bitset	qpp::exception::TypeMismatch, 360
qpp::Dynamic_bitset, 160	qpp::exception::UndefinedType, 362
ee	qpp::exception::Unknown, 364
	qpp::exception::ZeroSize, 370
qpp, 118	execute
egcd	qpp::QEngine, 309, 310
qpp, 50	qpp::QNoisyEngine, 318
eig	expandout
qpp, 51	qpp::Gates, 184, 185
elem_	experimental/experimental.h, 386
qpp::QCircuit::iterator, 226	expm
end	qpp, 54
qpp::QCircuit, 289, 290	
end_	FRED
qpp::Timer, 358	qpp::Bit_circuit, 134
qpp::internal::IOManipPointer, 212	qpp::Bit_circuit::Gate_count, 174
qpp::internal::IOManipRange, 215	qpp::Bit_circuit::Gate_depth, 179
entanglement	qpp::Gates, 192
qpp, 51, 52	factors
entanglement.h, 383	qpp, 54
-	·

Fd	get_dit
qpp::Gates, 186	qpp::QEngine, 310
fill_Ks_	get_dits
qpp::QuditDepolarizingNoise, 333	qpp::QEngine, 311
fill_probs_	get_duration
qpp::QuditDepolarizingNoise, 333	qpp::Timer, 357
first_	get_gate_count
qpp::internal::IOManipRange, 215	qpp::QCircuit, 293
flip	get_gate_depth
qpp::Dynamic_bitset, 162	qpp::QCircuit, 294
functions.h, 386 funm	get_gates_
qpp, 55	qpp::QCircuit, 294
αρρ , 33	get_instance
GHZ	qpp::internal::Singleton, 339
qpp::States, 348	get_last_idx
gate	qpp::NoiseBase, 252 get_last_K
qpp::QCircuit, 290, 291	qpp::NoiseBase, 252
gate_count	get_last_p
qpp::Bit_circuit, 136	qpp::NoiseBase, 252
gate_custom	
qpp::QCircuit, 291	get_measured qpp::QCircuit, 294, 295
Gate_depth	qpp::QEngine, 311
qpp::Bit_circuit::Gate_depth, 177, 178	-
gate_fan	get_measurement_count
qpp::QCircuit, 292, 293	qpp::QCircuit, 295
gate_hash_	get_measurements_
qpp::QCircuit::GateStep, 196	qpp::QCircuit, 296
gate_type_	get_name
qpp::QCircuit::GateStep, 196	qpp::Gates, 187
GateStep	qpp::QCircuit, 296
qpp::QCircuit::GateStep, 195	get_nc
GateType	qpp::QCircuit, 296
qpp::QCircuit, 281	get_noise_results
Gates	qpp::QNoisyEngine, 318
qpp::Gates, 183	get_non_measured
gates_	qpp::QCircuit, 296
qpp::QCircuit, 304	qpp::QEngine, 311
gates_ip_	get_nop_count
<pre>qpp::QCircuit::iterator::value_type_, 367</pre>	qpp::QCircuit, 297
gcd	get_nq
qpp, 55	qpp::QCircuit, 297
gconcurrence	get_num_subsys
qpp, 56	qpp::internal, 125
generated_	get_prng
qpp::NoiseBase, 254	qpp::RandomDevices, 336
get	get_probs
qpp::Dynamic_bitset, 163	qpp::NoiseBase, 253
get_Ks	qpp::QEngine, 312
qpp::NoiseBase, 252	get_psi
get_circuit	qpp::QEngine, 312
qpp::QEngine, 310	get_relative_pos_
get_cmat_hash_tbl_	qpp::QEngine, 312
qpp::QCircuit, 293	get_step_count
get_d	qpp::QCircuit, 297
qpp::NoiseBase, 251	get_thread_local_instance
qpp::QCircuit, 293	qpp::internal::Singleton, 339
get_dim_subsys	grams
qpp::internal, 125	qpp, 56, 57

Н	qpp::QCircuit::iterator::value_type_, 368
qpp::Gates, 192	isprime
hash_combine	qpp, 61
qpp::internal, 125	iterator
hash_eigen	qpp::QCircuit::iterator, 223
qpp, 58	iterator_category
heig	qpp::QCircuit::iterator, 222
qpp, 58 hevals	jn
qpp, 59	qpp::States, 345
hevects	dbbc.c.
qpp, 59	ket
11.17	qpp, 30
i_	kraus2choi
qpp::NoiseBase, 255	qpp, 61
IDisplay	kraus2super
qpp::IDisplay, 199	qpp, 62
IJSON	kron
qpp::IJSON, 202	qpp, 62–64
IOManipEigen	kron2
qpp::internal::IOManipEigen, 208 IOManipPointer	qpp::internal, 125
qpp::internal::IOManipPointer, 211	kronpow
IOManipRange	qpp, 64 Ks_
qpp::internal::IOManipRange, 214	qpp::NoiseBase, 255
Id	чррчовоевазо , 200
qpp::Gates, 187	last
ld2	qpp::internal::IOManipRange, 215
qpp::Gates, 193	lcm
idx	qpp, 65
qpp, 30	load
index_	qpp, 66
qpp::Dynamic_bitset, 163	qpp::RandomDevices, 336
infty	loadMATLAB
infty qpp, 118	loadMATLAB qpp, 66, 67
infty qpp, 118 Init	loadMATLAB qpp, 66, 67 logdet
infty qpp, 118 Init qpp::Init, 204	loadMATLAB qpp, 66, 67 logdet qpp, 68
infty	loadMATLAB qpp, 66, 67 logdet qpp, 68 logm
infty qpp, 118 Init qpp::Init, 204 input_output.h, 391 instruments.h, 392	loadMATLAB qpp, 66, 67 logdet qpp, 68 logm qpp, 68
infty	loadMATLAB
infty	loadMATLAB qpp, 66, 67 logdet qpp, 68 logm qpp, 68
infty	loadMATLAB

MeasureType	noise_type
qpp::QCircuit, 282	qpp::NoiseBase, 249
measured_	NoiseBase
qpp::QCircuit, 304	qpp::NoiseBase, 250
measurement_count_	none
qpp::QCircuit, 304	qpp::Dynamic_bitset, 163
measurement_type_	nop
qpp::QCircuit::MeasureStep, 245	qpp::QCircuit, 299
measurements	norm
qpp::QCircuit, 304	qpp, 83
measurements_ip_	normalize
qpp::QCircuit::iterator::value_type_, 368	qpp, 83
measureV	nq_
qpp::QCircuit, 297, 298	qpp::QCircuit, 305
measureZ	number_theory.h, 397
qpp::QCircuit, 298	
mes	offset_
qpp::States, 345	qpp::Dynamic_bitset, 164
minus	omega
_	qpp, 84
qpp::States, 346 mket	one
	qpp::States, 346
qpp, 77, 78	operations.h, 399
modiny	operator!=
qpp, 78	qpp::Dynamic_bitset, 164
modmul	qpp::QCircuit::iterator, 223
qpp, 79	operator<<
modpow	qpp::IDisplay, 200
qpp, 79	
mprj	qpp::QCircuit, 302, 303
qpp, 80	operator*
msg_	qpp::QCircuit::iterator, 224
qpp::exception::Exception, 173	operator()
multiidx2n	qpp::NoiseBase, 253, 254
qpp, 81	qpp::internal::EqualEigen, 169
qpp::internal, 126	qpp::internal::HashEigen, 197
0 1111	operator++
n2multiidx	qpp::QCircuit::iterator, 224
qpp, 81	operator-
qpp::internal, 126	qpp::Dynamic_bitset, 164
N_	operator=
qpp::internal::IOManipPointer, 212	qpp::Bit_circuit::Gate_depth, 178
n_	qpp::IDisplay, 200
qpp::Dynamic_bitset, 168	qpp::IJSON, 202
NOT	qpp::QCircuit::iterator, 224
qpp::Bit_circuit, 134	<pre>qpp::QCircuit::iterator::value_type_, 367</pre>
qpp::Bit_circuit::Gate_count, 174	qpp::QEngine, 313
qpp::Bit_circuit::Gate_depth, 180	qpp::Timer, 357
name_	qpp::internal::IOManipPointer, 211
qpp::QCircuit, 305	qpp::internal::IOManipRange, 214
qpp::QCircuit::GateStep, 196	qpp::internal::Singleton, 339
qpp::QCircuit::MeasureStep, 245	operator==
nc_	qpp::Dynamic_bitset, 165
qpp::QCircuit, 305	qpp::QCircuit::iterator, 225
negativity	operator"" _bra
qpp, 82	qpp::literals, 127
noise	operator"" _i
qpp::QNoisyEngine, 319	qpp, 84
noise_results_	qpp::literals, 127
qpp::QNoisyEngine, 319	operator"" _ket
-II-1 / ·g····-, - · ·	=

qpp::literals, 128	qpp::QCircuit, 282
operator"" _prj	QEngine
qpp::literals, 128	qpp::QCircuit, 303
	qpp::QEngine, 308, 309
P	QFT
qpp::internal::IOManipPointer, 212	qpp, 90
pGHZ	qpp::QCircuit, 299, 300
qpp::States, 349	QNoisyEngine
pb00	qpp::QNoisyEngine, 317
qpp::States, 348 pb01	QPP_UNUSED_
qpp::States, 348	qpp.h, 403
pb10	qc_
qpp::States, 349	qpp::QCircuit::iterator, 226
pb11	qpp::QEngine, 315
qpp::States, 349	qmutualinfo
pi	qpp, 91
qpp, 118	qpp, 15
plus	absm, 31
qpp::States, 346	abssq, 31, 32
pointer	adjoint, 32
qpp::QCircuit::iterator, 222	anticomm, 33 apply, 33–35
powm	applyCTRL, 36
qpp, 84	applyQFT, 37
prj	applyTFQ, 38
qpp, 85	avg, 38
prng_	bigint, 28
qpp::RandomDevices, 337	bloch2rho, 38
probs_	bra, 28
qpp::NoiseBase, 255	choi2kraus, 39
qpp::QEngine, 315	choi2super, 39
prod	chop, 118
qpp, 85, 86	cmat, 29
psi_	comm, 40
qpp::QEngine, 315	complement, 40
ptrace	compperm, 41
qpp, 86, 87	concurrence, 41
ptrace1	conjugate, 42
qpp, 87, 88 ptrace2	contfrac2x, 42
qpp, 88, 89	convergents, 42, 43
ptranspose	cor, 43
qpp, 89, 90	cosm, 44
pW	cov, 44
qpp::States, 349	cplx, 29
px0	cwise, 45
qpp::States, 349	det, 45
px1	dirsum, 46, 47
qpp::States, 349	dirsumpow, 47
py0	disp, 48–50
qpp::States, 350	dmat, 29
py1	dyn_col_vect, 29
qpp::States, 350	dyn_mat, 29
pz0	dyn_row_vect, 30
qpp::States, 350	ee, 118
pz1	egcd, 50
qpp::States, 350	eig, 51
OCircuit	entanglement, 51, 52
QCircuit	entropy, 52, 53

evals, 53	randidx, 95
evects, 53	randket, 95
expm, 54	randkraus, 95
factors, 54	randn, 96, 97
funm, 55	randperm, 98
gcd, 55	randprime, 98
gconcurrence, 56	randprob, 99
grams, 56, 57	randrho, 99
hash_eigen, 58	randU, 99
heig, 58	randV, 100
hevals, 59	renyi, 100, 101
hevects, 59	reshape, 101
idx, 30	rho2bloch, 102
infty, 118	rho2pure, 102
inverse, 59	save, 103
invperm, 60	saveMATLAB, 103, 104
ip, 60, 61	schatten, 104
isprime, 61	schmidtA, 105
ket, 30	schmidtB, 105, 106
kraus2choi, 61	schmidtcoeffs, 106, 107
kraus2super, 62	schmidtprobs, 107, 108
kron, 62–64	sigma, 108
	sinm, 109
kronpow, 64	
lcm, 65	spectralpowm, 109
load, 66	sqrtm, 110
loadMATLAB, 66, 67	sum, 110, 111
logdet, 68	super2choi, 111
logm, 68	svals, 112
lognegativity, 69	svd, 112
marginalX, 69	svdU, 112
marginalY, 71	svdV, 113
maxn, 118	syspermute, 113, 114
measure, 71–76	TFQ, 114
measure_seq, 76, 77	to_void, 30
mket, 77, 78	trace, 114
modinv, 78	transpose, 115
modmul, 79	tsallis, 115, 116
modpow, 79	uniform, 116
mprj, 80	var, 117
multiidx2n, 81	x2contfrac, 117
n2multiidx, 81	qpp.h, 401
negativity, 82	QPP_UNUSED_, 403
norm, 83	qpp::Bit_circuit, 131
normalize, 83	Bit_circuit, 133
omega, 84	CNOT, 134
operator"" _i, 84	FRED, 134
pi, 118	gate_count, 136
powm, 84	NOT, 134
prj, 85	reset, 135
prod, 85, 86	SWAP, 135
ptrace, 86, 87	TOF, 136
ptrace1, 87, 88	this, 137
ptrace2, 88, 89	X, 136
ptranspose, 89, 90	qpp::Bit_circuit::Gate_count, 173
QFT, 90	CNOT, 174
qmutualinfo, 91	FRED, 174
rand, 92–94	NOT, 174
randH, 94	reset, 174
ianun, 34	16561, 174

SWAP, 174	CNOTba, 192
TOF, 174	CNOT, 192
total, 175	CTRL, 184
X, 175	CZ, 192
qpp::Bit_circuit::Gate_depth, 175	expandout, 184, 185
bCNOT, 178	FRED, 192
bFRED, 178	Fd, 186
bNOT, 179	Gates, 183
•	
bSWAP, 179	get_name, 187
bTOF, 179	H, 192
Bit_circuit, 179	ld, 187
bit_circuit_, 179	ld2, 193
btotal, 179	internal::Singleton< const Gates >, 192
CNOT, 179	MODMUL, 187
FRED, 179	Rn, 188
Gate_depth, 177, 178	RX, 188
NOT, 180	RY, 189
operator=, 178	RZ, 189
reset, 178	S, 193
SWAP, 180	SWAPd, 189
TOF, 180	SWAP, 193
total, 180	T, 193
X, 180	TOF, 193
qpp::Codes, 137	X, 193
~Codes, 139	Xd, 191
Codes, 139	Y, 194
codeword, 139	Z, 194
internal::Singleton< const Codes >, 139	Zd, 191
Type, 138	qpp::IDisplay, 198
qpp::Dynamic_bitset, 158	∼IDisplay, 199
~Dynamic_bitset, 161	display, 200
all, 161	IDisplay, 199
any, 161	operator<<, 200
count, 161	operator=, 200
data, 161	qpp::IJSON, 201
display, 162	\sim IJSON, 202
Dynamic_bitset, 160	IJSON, 202
flip, 162	operator=, 202
get, 163	to_JSON, 203
index_, 163	qpp::Init, 203
n_, 168	\sim Init, 204
none, 163	Init, 204
offset_, 164	internal::Singleton < const Init >, 205
operator!=, 164	qpp::NoiseBase
operator-, 164	\sim NoiseBase, 250
operator==, 165	compute_probs_, 251
rand, 165, 166	compute_state_, 251
reset, 166	d_, 254
set, 166, 167	generated_, 254
	get_Ks, 252
size, 167	- -
storage_size, 167	get_d, 251
storage_size_, 168	get_last_idx, 252
storage_type, 160	get_last_K, 252
to_string, 167	get_last_p, 252
v_, 168	get_probs, 253
value_type, 160	i_, 255
qpp::Gates, 181	Ks_, 255
\sim Gates, 183	noise_type, 249

NoiseBase, 250	TFQ, 300, 301
operator(), 253, 254	to_JSON, 301
probs_, 255	qpp::QCircuit::GateStep, 194
qpp::NoiseBase< T >, 248	ctrl_, 196
qpp::NoiseType, 255	gate_hash_, 196
qpp::NoiseType::StateDependent, 342	gate_type_, 196
qpp::NoiseType::StateIndependent, 342	GateStep, 195
qpp::QCircuit, 276	name_, 196
∼QCircuit, 283	target_, 196
add_hash_, 283	qpp::QCircuit::MeasureStep, 243
begin, 283	c_reg_, 245
cCTRL_custom, 286	mats_hash_, 245
cCTRL, 284, 285	MeasureStep, 244
CTRL_custom, 289	measurement_type_, 245
CTRL, 287, 288	name_, 245
cbegin, 284	target_, 245
cend, 286	qpp::QCircuit::iterator, 221
cmat_hash_tbl_, 303	difference_type, 222
const_iterator, 281	elem_, 226
count_, 304	iterator, 223
d_, 304	iterator_category, 222
display, 289	operator!=, 223
end, 289, 290	operator*, 224
gate, 290, 291	operator++, 224
gate_custom, 291	operator=, 224
gate_fan, 292, 293	operator==, 225
GateType, 281	pointer, 222
gates_, 304	qc_, 226
get_cmat_hash_tbl_, 293	reference, 223
get_d, 293	set_begin_, 225
get_gate_count, 293	set_end_, 225
get_gate_depth, 294	value_type, 223
get_gates_, 294	qpp::QCircuit::iterator::value_type_, 365
get_measured, 294, 295	display, 367
get_measurement_count, 295 get_measurements , 296	gates_ip_, 367
<u> </u>	ip_, 368
get_name, 296	measurements_ip_, 368
get_nc, 296 get_non_measured, 296	operator=, 367 type_, 368
get nop count, 297	value type , 366, 367
get_nq, 297	value_type_, 366, 367 value_type_qc_, 368
get step count, 297	qpp::QEngine, 306
MeasureType, 282	∼QEngine, 309
measured, 304	display, 309
measurement_count_, 304	dis_, 315
measurements_, 304	execute, 309, 310
measureV, 297, 298	get_circuit, 310
measureZ, 298	get_dit, 310
name_, 305	get_dits, 311
nc_, 305	get_measured, 311
nop, 299	get_non_measured, 311
nq_, 305	get_probs, 312
operator<<, 302, 303	get_probs, 312 get_psi, 312
QCircuit, 282	get_relative_pos_, 312
QEngine, 303	operator=, 313
QFT, 299, 300	probs_, 315
step_types_, 305	psi_, 315
StepType, 282	QEngine, 308, 309
()	

qc_, 315	px0, 349
reset, 313	px1, 349
set_dit, 313	py0, 350
set_measured_, 313	py1, 350
set_psi, 314	pz0, 350
subsys_, 315	pz1, 350
to_JSON, 314	States, 345
qpp::QNoisyEngine	W, 350
execute, 318	x0, 350
get_noise_results, 318	x1, 351
noise_, 319	y0, 351
noise_results_, 319	y1, 351
QNoisyEngine, 317	z0, <mark>351</mark>
qpp::QNoisyEngine < NoiseModel >, 316	z1, 351
qpp::QubitAmplitudeDampingNoise, 320	zero, 347
QubitAmplitudeDampingNoise, 321	qpp::Timer
qpp::QubitBitFlipNoise, 321	\sim Timer, 356
QubitBitFlipNoise, 322	display, 356
qpp::QubitBitPhaseFlipNoise, 323	• •
QubitBitPhaseFlipNoise, 324	end_, 358
•	get_duration, 357
qpp::QubitDepolarizingNoise, 324	operator=, 357
QubitDepolarizingNoise, 325	start_, 358
qpp::QubitPhaseDampingNoise, 326	tic, 357
QubitPhaseDampingNoise, 327	tics, 358
qpp::QubitPhaseFlipNoise, 327	Timer, 355, 356
QubitPhaseFlipNoise, 328	toc, 358
qpp::QuditDepolarizingNoise, 331	qpp::Timer< T, CLOCK_T >, 354
fill_Ks_, 333	qpp::exception, 118
fill_probs_, 333	qpp::exception::CustomException, 140
QuditDepolarizingNoise, 332	CustomException, 141
qpp::RandomDevices, 334	type_description, 142
\sim RandomDevices, 335	what_, 142
get_prng, 336	qpp::exception::DimsInvalid, 143
internal::Singleton < RandomDevices >, 337	Exception, 144
load, 336	type_description, 144
prng_, 337	qpp::exception::DimsMismatchCvector, 145
RandomDevices, 335	Exception, 146
rd_, 337	type_description, 146
save, 336	qpp::exception::DimsMismatchMatrix, 147
qpp::States, 342	Exception, 148
\sim States, 345	type_description, 148
b00, 347	qpp::exception::DimsMismatchRvector, 149
b01, 348	Exception, 150
b10, 348	type_description, 150
b11, 348	qpp::exception::DimsMismatchVector, 151
GHZ, 348	Exception, 152
internal::Singleton< const States >, 347	type_description, 152
jn, 345	qpp::exception::DimsNotEqual, 153
mes, 345	Exception, 154
minus, 346	type_description, 154
one, 346	qpp::exception::Duplicates, 156
pGHZ, 349	Exception, 157
pb00, 348	type_description, 157
pb00, 348 pb01, 348	qpp::exception::Exception, 170
pb01, 349 pb10, 349	Exception, 172
pb10, 349 pb11, 349	
•	msg_, 173
plus, 346 pW, 349	type_description, 172
μνν, 343	what, 172

where_, 173	qpp::exception::PermMismatchDims, 274
qpp::exception::InvalidIterator, 205	Exception, 275
Exception, 206	type_description, 276
type_description, 207	qpp::exception::QuditAlreadyMeasured, 329
qpp::exception::MatrixMismatchSubsys, 227	Exception, 330
Exception, 228	type_description, 331
•	
type_description, 229	qpp::exception::SizeMismatch, 340
qpp::exception::MatrixNotCvector, 229	Exception, 341
Exception, 230	type_description, 341
type_description, 231	qpp::exception::SubsysMismatchDims, 352
qpp::exception::MatrixNotRvector, 231	Exception, 353
Exception, 232	type_description, 353
type_description, 233	qpp::exception::TypeMismatch, 359
qpp::exception::MatrixNotSquare, 233	Exception, 360
Exception, 234	type_description, 361
type_description, 235	qpp::exception::UndefinedType, 361
qpp::exception::MatrixNotSquareNorCvector, 235	Exception, 362
Exception, 236	type_description, 363
type_description, 237	qpp::exception::Unknown, 363
qpp::exception::MatrixNotSquareNorRvector, 237	Exception, 364
Exception, 238	type_description, 365
type_description, 239	qpp::exception::ZeroSize, 369
qpp::exception::MatrixNotSquareNorVector, 239	Exception, 370
Exception, 240	type_description, 370
type_description, 241	qpp::experimental, 120
qpp::exception::MatrixNotVector, 241	qpp::internal, 120
Exception, 242	check_cvector, 122
type_description, 243	check_dims, 122
qpp::exception::NoCodeword, 246	check_dims_match_cvect, 122
Exception, 247	check_dims_match_mat, 122
type_description, 247	check_dims_match_rvect, 122
qpp::exception::NotBipartite, 256	check_eq_dims, 123
Exception, 257	check_matching_sizes, 123
type_description, 258	check_no_duplicates, 123
qpp::exception::NotImplemented, 258	check_nonzero_size, 123
Exception, 259	check_perm, 123
type description, 260	check_qubit_cvector, 123
qpp::exception::NotQubitCvector, 260	check_qubit_evector, 123
Exception, 261	check_qubit_matrix, 124
type_description, 262	check_qubit_vector, 124
• • • •	— · —
qpp::exception::NotQubitMatrix, 262	check_rvector, 124
Exception, 263	check_square_mat, 124
type_description, 264	check_subsys_match_dims, 124
qpp::exception::NotQubitRvector, 264	check_vector, 125
Exception, 265	dirsum2, 125
type_description, 266	get_dim_subsys, 125
qpp::exception::NotQubitSubsys, 266	get_num_subsys, 125
Exception, 267	hash_combine, 125
type_description, 268	kron2, 125
qpp::exception::NotQubitVector, 268	multiidx2n, 126
Exception, 269	n2multiidx, 126
type_description, 270	variadic_vector_emplace, 126
qpp::exception::OutOfRange, 270	qpp::internal::Display_Impl_, 155
Exception, 271	display_impl_, 155
type_description, 272	qpp::internal::EqualEigen, 169
qpp::exception::PermInvalid, 272	operator(), 169
Exception, 273	qpp::internal::HashEigen, 197
type_description, 274	operator(), 197

qpp::internal::IOManipEigen, 207	QubitPhaseFlipNoise
A_, 209	qpp::QubitPhaseFlipNoise, 328
chop_, 209	QuditDepolarizingNoise
display, 209	qpp::QuditDepolarizingNoise, 332
IOManipEigen, 208	
qpp::internal::IOManipPointer	rand
display, 211	qpp, 92–94
end_, 212	qpp::Dynamic_bitset, 165, 166
IOManipPointer, 211	randH
N_, 212	qpp, 94
operator=, 211	randidx
•	qpp, 95
p_, 212	randket
separator_, 212	qpp, 95
start_, 212	randkraus
qpp::internal::IOManipPointer< PointerType >, 210	qpp, 95
qpp::internal::IOManipRange	randn
display, 214	qpp, 96, 97
end_, 215	random.h, 403
first_, 215	RandomDevices
IOManipRange, 214	qpp::RandomDevices, 335
last_, 215	randperm
operator=, 214	•
separator_, 215	qpp, 98
start_, 215	randprime
qpp::internal::IOManipRange< InputIterator >, 213	qpp, 98
qpp::internal::Singleton	randprob
~Singleton, 339	qpp, 99
get_instance, 339	randrho
get_thread_local_instance, 339	qpp, 99
operator=, 339	randU
Singleton, 338, 339	qpp, 99
_	randV
app::internal::Singleton < T >, 337	qpp, 100
qpp::is_complex< std::complex< T >>, 217	rd_
qpp::is_complex < T >, 216	qpp::RandomDevices, 337
qpp::is_iterable< T, to_void< decltype(std::declval< T	reference
>().begin()), decltype(std::declval< T >().↔	qpp::QCircuit::iterator, 223
end()), decltype(*(std::declval< T >(). ↔	renyi
begin()))>>, 219	qpp, 100, 101
qpp::is_iterable< T, typename >, 218	reset
qpp::is_matrix_expression< Derived >, 220	qpp::Bit_circuit, 135
qpp::literals, 127	qpp::Bit_circuit::Gate_count, 174
operator"" _bra, 127	qpp::Bit_circuit::Gate_depth, 178
operator"" _bra, 127 operator"" _i, 127 operator"" _ket, 128 operator"" _prj, 128	qpp::Dynamic_bitset, 166
operator"" _ket, 128	qpp::QEngine, 313
operator"" _prj, 128	reshape
qpp::make_void	qpp, 101
type, 227	rho2bloch
qpp::make_void< Ts >, 226	qpp, 102
QubitAmplitudeDampingNoise	rho2pure
qpp::QubitAmplitudeDampingNoise, 321	qpp, 102
QubitBitFlipNoise	Rn
qpp::QubitBitFlipNoise, 322	qpp::Gates, 188
QubitBitPhaseFlipNoise	RX
qpp::QubitBitPhaseFlipNoise, 324	
QubitDepolarizingNoise	qpp::Gates, 188
•	
qpp::QubitDepolarizingNoise, 325	qpp::Gates, 189
QubitPhaseDampingNoise	RZ
qpp::QubitPhaseDampingNoise, 327	qpp::Gates, 189

S	step_types_
qpp::Gates, 193	qpp::QCircuit, 305
SWAPd	StepType
qpp::Gates, 189	qpp::QCircuit, 282
SWAP	storage size
qpp::Bit_circuit, 135	qpp::Dynamic_bitset, 167
qpp::Bit_circuit::Gate_count, 174	storage_size_
qpp::Bit_circuit::Gate_depth, 180	qpp::Dynamic_bitset, 168
qpp::Gates, 193	storage_type
save	qpp::Dynamic_bitset, 160
qpp, 103	subsys_
qpp::RandomDevices, 336	qpp::QEngine, 315
saveMATLAB	sum
qpp, 103, 104	qpp, 110, 111
schatten	super2choi
qpp, 104	qpp, 111
schmidtA	svals
	qpp, 112
qpp, 105 schmidtB	svd
	qpp, 112
qpp, 105, 106	svdU
schmidtcoeffs	
qpp, 106, 107	qpp, 112 svdV
schmidtprobs	
qpp, 107, 108	qpp, 113
separator_	syspermute
qpp::internal::IOManipPointer, 212	qpp, 113, 114
qpp::internal::IOManipRange, 215	-
set	T
qpp::Dynamic_bitset, 166, 167	qpp::Gates, 193
set_begin_	TFQ
	qpp, 114
qpp::QCircuit::iterator, 225	qpp::QCircuit, 300, 301
set_dit	TOF
qpp::QEngine, 313	qpp::Bit_circuit, 136
set_end_	qpp::Bit_circuit::Gate_count, 174
qpp::QCircuit::iterator, 225	qpp::Bit_circuit::Gate_depth, 180
set_measured_	qpp::Gates, 193
qpp::QEngine, 313	target_
set_psi	qpp::QCircuit::GateStep, 196
qpp::QEngine, 314	qpp::QCircuit::MeasureStep, 245
sigma	this
qpp, 108	
Singleton	qpp::Bit_circuit, 137
qpp::internal::Singleton, 338, 339	tic Time 257
sinm	qpp::Timer, 357
	tics
qpp, 109	qpp::Timer, 358
size	Timer
qpp::Dynamic_bitset, 167	qpp::Timer, 355, 356
spectralpowm	to_JSON
qpp, 109	qpp::IJSON, 203
sqrtm	qpp::QCircuit, 301
qpp, 110	qpp::QEngine, 314
start_	to_string
qpp::Timer, 358	qpp::Dynamic_bitset, 167
qpp::internal::IOManipPointer, 212	to_void
qpp::internal::IOManipRange, 215	qpp, 30
States	toc
qpp::States, 345	qpp::Timer, 358
statistics.h, 405	total

	<pre>qpp::Bit_circuit::Gate_count, 175 qpp::Bit_circuit::Gate_depth, 180</pre>	valu	e_type qpp::Dynamic_bitset, 160
trace)		qpp::QCircuit::iterator, 223
	qpp, 114	valu	e_type_
traits	s.h, 406		qpp::QCircuit::iterator::value_type_, 366, 367
trans	spose	valu	e_type_qc_
	qpp, 115		qpp::QCircuit::iterator::value_type_, 368
tsalli	S	var	
	qpp, 115, 116		qpp, 117
Type		varia	adic_vector_emplace
	qpp::Codes, 138		qpp::internal, 126
type			
	qpp::make_void, 227	W	
type	_		qpp::States, 350
	qpp::QCircuit::iterator::value_type_, 368	wha	
type	_description		qpp::exception::Exception, 172
	qpp::exception::CustomException, 142	wha	_
	qpp::exception::DimsInvalid, 144		qpp::exception::CustomException, 142
	qpp::exception::DimsMismatchCvector, 146	whe	
	qpp::exception::DimsMismatchMatrix, 148		qpp::exception::Exception, 173
	qpp::exception::DimsMismatchRvector, 150	V	
	qpp::exception::DimsMismatchVector, 152	X	amanuDit singuit 100
	qpp::exception::DimsNotEqual, 154		qpp::Bit_circuit, 136
	qpp::exception::Duplicates, 157		qpp::Bit_circuit::Gate_count, 175
	qpp::exception::Exception, 172		qpp::Bit_circuit::Gate_depth, 180
	qpp::exception::InvalidIterator, 207	x0	qpp::Gates, 193
	qpp::exception::MatrixMismatchSubsys, 229	ΧU	annii Statos 250
	qpp::exception::MatrixNotCvector, 231	x1	qpp::States, 350
	qpp::exception::MatrixNotRvector, 233	ΧI	qpp::States, 351
	qpp::exception::MatrixNotSquare, 235	v2cc	ontfrac
	qpp::exception::MatrixNotSquareNorCvector, 237	X200	qpp, 117
	qpp::exception::MatrixNotSquareNorRvector, 239	Xd	чрр, 117
	qpp::exception::MatrixNotSquareNorVector, 241	Λu	qpp::Gates, 191
	qpp::exception::MatrixNotVector, 243		dppdates, 101
	qpp::exception::NoCodeword, 247	Υ	
	qpp::exception::NotBipartite, 258		qpp::Gates, 194
	qpp::exception::NotImplemented, 260	y0	
	qpp::exception::NotQubitCvector, 262	•	qpp::States, 351
	qpp::exception::NotQubitMatrix, 264	y1	
	app::exception::NotQubitRvector, 266	-	qpp::States, 351
	app::exception::NotQubitSubsys, 268		
	qpp::exception::NotQubitVector, 270 qpp::exception::OutOfRange, 272	Z	
	qpp::exception::OutOrnange, 272 qpp::exception::PermInvalid, 274		qpp::Gates, 194
	qpp::exception::PermMismatchDims, 276	z0	
	qpp::exception::QuditAlreadyMeasured, 331		qpp::States, 351
	qpp::exception::Qualitativeacyweasured, 331 qpp::exception::SizeMismatch, 341	z1	
	qpp::exception::SizeWishfatch, 341 qpp::exception::SubsysMismatchDims, 353		qpp::States, 351
	qpp::exception::TypeMismatch, 361	Zd	
	app::exception::Typewismatch, 307		qpp::Gates, 191
	app::exception::Unknown, 365	zero	
	qpp::exception::ZeroSize, 370		qpp::States, 347
tyne	s.h, 407		
., po.	, ·•·		
unifo	rm		
	qpp, 116		
v _			
	qpp::Dynamic_bitset, 168		