Quantum++ v1.1

Generated by Doxygen 1.8.14

Contents

1	Qua	ntum++																	1
2	Nam	nespace	space Index 3																
	2.1	Names	space List									 	 		 	 	 		 3
3	Hier	archica	l Index																5
	3.1	Class	Hierarchy									 	 		 	 	 		 5
4	Clas	s Index																	7
	4.1	Class	List									 	 		 	 	 		 7
5	File	Index																	11
	5.1	File Lis	st									 	 		 	 	 		 11
6	Nam	nespace	Docume	nta	tion														13
	6.1	qpp Na	amespace	Re	ferer	nce .						 	 		 	 	 		 13
		6.1.1	Detailed	De	scrip	tion						 	 		 	 	 		 26
		6.1.2	Typedef	Dod	cume	entati	on .					 	 		 	 	 		 26
			6.1.2.1	bi	igint							 	 		 	 	 		 26
			6.1.2.2	bı	ra .							 	 		 	 	 		 26
			6.1.2.3	CI	mat							 	 		 	 	 		 27
			6.1.2.4	c	plx .							 	 		 	 	 		 27
			6.1.2.5	dı	mat							 	 		 		 		 27
			6.1.2.6	dy	yn_c	ol_ve	ect .					 	 		 		 		 27
			6.1.2.7	dy	yn_m	nat .						 	 		 	 	 		 27
			6.1.2.8	d	vn ro	ow v	ect					 	 		 	 	 		 28

ii CONTENTS

	6.1.2.9	idx	28
	6.1.2.10	ket	28
	6.1.2.11	to_void	28
6.1.3	Function	Documentation	28
	6.1.3.1	absm()	28
	6.1.3.2	abssq() [1/3]	29
	6.1.3.3	abssq() [2/3]	29
	6.1.3.4	abssq() [3/3]	30
	6.1.3.5	adjoint()	30
	6.1.3.6	anticomm()	30
	6.1.3.7	apply() [1/5]	31
	6.1.3.8	apply() [2/5]	31
	6.1.3.9	apply() [3/5]	32
	6.1.3.10	apply() [4/5]	32
	6.1.3.11	apply() [5/5]	33
	6.1.3.12	applyCTRL() [1/2]	33
	6.1.3.13	applyCTRL() [2/2]	34
	6.1.3.14	applyQFT()	35
	6.1.3.15	applyTFQ()	35
	6.1.3.16	avg()	36
	6.1.3.17	bloch2rho()	36
	6.1.3.18	choi2kraus()	37
	6.1.3.19	choi2super()	37
	6.1.3.20	comm()	38
	6.1.3.21	complement()	38
	6.1.3.22	compperm()	38
	6.1.3.23	concurrence()	40
	6.1.3.24	conjugate()	40
	6.1.3.25	contfrac2x()	41
	6.1.3.26	convergents() [1/2]	41

6.1.3.27	convergents() [2/2]	42
6.1.3.28	cor()	42
6.1.3.29	cosm()	43
6.1.3.30	cov()	43
6.1.3.31	cwise()	43
6.1.3.32	det()	44
6.1.3.33	dirsum() [1/4]	44
6.1.3.34	dirsum() [2/4]	45
6.1.3.35	dirsum() [3/4]	45
6.1.3.36	dirsum() [4/4]	46
6.1.3.37	dirsumpow()	46
6.1.3.38	disp() [1/5]	47
6.1.3.39	disp() [2/5]	47
6.1.3.40	disp() [3/5]	47
6.1.3.41	disp() [4/5]	48
6.1.3.42	disp() [5/5]	48
6.1.3.43	egcd()	49
6.1.3.44	eig()	49
6.1.3.45	entanglement() [1/2]	50
6.1.3.46	entanglement() [2/2]	50
6.1.3.47	entropy() [1/2]	51
6.1.3.48	entropy() [2/2]	51
6.1.3.49	evals()	52
6.1.3.50	evects()	52
6.1.3.51	expm()	52
6.1.3.52	factors()	53
6.1.3.53	funm()	53
6.1.3.54	gcd() [1/2]	54
6.1.3.55	gcd() [2/2]	54
6.1.3.56	gconcurrence()	55

iv CONTENTS

6.1.3.57	grams() [1/3]	55
6.1.3.58	grams() [2/3]	55
6.1.3.59	grams() [3/3]	56
6.1.3.60	heig()	56
6.1.3.61	hevals()	57
6.1.3.62	hevects()	57
6.1.3.63	inverse()	58
6.1.3.64	invperm()	58
6.1.3.65	ip() [1/2]	58
6.1.3.66	ip() [2/2]	59
6.1.3.67	isprime()	59
6.1.3.68	kraus2choi()	60
6.1.3.69	kraus2super()	60
6.1.3.70	kron() [1/4]	61
6.1.3.71	kron() [2/4]	61
6.1.3.72	kron() [3/4]	62
6.1.3.73	kron() [4/4]	62
6.1.3.74	kronpow()	62
6.1.3.75	lcm() [1/2]	63
6.1.3.76	lcm() [2/2]	63
6.1.3.77	load()	64
6.1.3.78	loadMATLAB() [1/2]	64
6.1.3.79	loadMATLAB() [2/2]	65
6.1.3.80	logdet()	66
6.1.3.81	logm()	66
6.1.3.82	lognegativity() [1/2]	67
6.1.3.83	lognegativity() [2/2]	67
6.1.3.84	marginalX()	67
6.1.3.85	marginalY()	69
6.1.3.86	measure() [1/9]	69

6.1.3.87 measure() [2/9]	70
6.1.3.88 measure() [3/9]	70
6.1.3.89 measure() [4/9]	70
6.1.3.90 measure() [5/9]	'1
6.1.3.91 measure() [6/9]	2
6.1.3.92 measure() [7/9]	72
6.1.3.93 measure() [8/9]	73
6.1.3.94 measure() [9/9]	74
6.1.3.95 measure_seq() [1/2]	⁷ 4
6.1.3.96 measure_seq() [2/2]	75
6.1.3.97 mket() [1/2]	75
6.1.3.98 mket() [2/2]	76
6.1.3.99 modinv()	76
6.1.3.100 modmul()	7
6.1.3.101 modpow()	7
6.1.3.102 mprj() [1/2]	78
6.1.3.103 mprj() [2/2]	79
6.1.3.104 multiidx2n()	79
6.1.3.105 n2multiidx()	30
6.1.3.106 negativity() [1/2]	30
6.1.3.107 negativity() [2/2]	30
6.1.3.108 norm()	31
6.1.3.109 normalize()	31
6.1.3.110 omega()	32
6.1.3.111 operator""""_i()	32
6.1.3.112 powm()	32
6.1.3.113 prj()	33
6.1.3.114 prod() [1/3]	33
6.1.3.115 prod() [2/3]	34
6.1.3.116 prod() [3/3]	34

vi

6.1.3.117 ptrace() [1/2]
6.1.3.118 ptrace() [2/2]
6.1.3.119 ptrace1() [1/2]
6.1.3.120 ptrace1() [2/2]
6.1.3.121 ptrace2() [1/2]
6.1.3.122 ptrace2() [2/2]
6.1.3.123 ptranspose() [1/2]
6.1.3.124 ptranspose() [2/2]
6.1.3.125 QFT()
6.1.3.126 qmutualinfo() [1/2]
6.1.3.127 qmutualinfo() [2/2]
6.1.3.128 rand() [1/5] 90
6.1.3.129 rand() [2/5] 90
6.1.3.130 rand() [3/5] 91
6.1.3.131 rand() [4/5] 91
6.1.3.132 rand() [5/5]
6.1.3.133 randH()
6.1.3.134 randidx()
6.1.3.135 randket()
6.1.3.136 randkraus()
6.1.3.137 randn() [1/4] 94
6.1.3.138 randn() [2/4] 94
6.1.3.139 randn() [3/4]
6.1.3.140 randn() [4/4]
6.1.3.141 randperm()
6.1.3.142 randprime()
6.1.3.143 randprob()
6.1.3.144 randrho()
6.1.3.145 randU()
6.1.3.146 randV()

CONTENTS vii

6.1.3.147 renyi() [1/2]
6.1.3.148 renyi() [2/2]
6.1.3.149 reshape()
6.1.3.150 rho2bloch()
6.1.3.151 rho2pure()
6.1.3.152 save()
6.1.3.153 saveMATLAB() [1/2]
6.1.3.154 saveMATLAB() [2/2]
6.1.3.155 schatten()
6.1.3.156 schmidtA() [1/2]
6.1.3.157 schmidtA() [2/2]
6.1.3.158 schmidtB() [1/2]
6.1.3.159 schmidtB() [2/2]
6.1.3.160 schmidtcoeffs() [1/2]
6.1.3.161 schmidtcoeffs() [2/2]
6.1.3.162 schmidtprobs() [1/2]
6.1.3.163 schmidtprobs() [2/2]
6.1.3.164 sigma()
6.1.3.165 sinm()
6.1.3.166 spectralpowm()
6.1.3.167 sqrtm()
6.1.3.168 sum() [1/3]
6.1.3.169 sum() [2/3]
6.1.3.170 sum() [3/3]
6.1.3.171 super2choi()
6.1.3.172 svals()
6.1.3.173 svd()
6.1.3.174 svdU()
6.1.3.175 svdV()
6.1.3.176 syspermute() [1/2]

viii CONTENTS

		6.1.3.177	7 syspermute() [2/2]	112
		6.1.3.178	8 TFQ()	112
		6.1.3.179	9 trace()	113
		6.1.3.180	0 transpose()	113
		6.1.3.181	1 tsallis() [1/2]	113
		6.1.3.182	2 tsallis() [2/2]	114
		6.1.3.183	3 uniform()	114
		6.1.3.184	4 var()	115
		6.1.3.185	5 x2contfrac()	115
	6.1.4	Variable	Documentation	116
		6.1.4.1	chop	116
		6.1.4.2	ee	116
		6.1.4.3	eps	116
		6.1.4.4	idx_infty	116
		6.1.4.5	infty	116
		6.1.4.6	maxn	117
		6.1.4.7	pi	117
6.2	qpp::ex	ception N	lamespace Reference	117
	6.2.1	Detailed	Description	118
6.3	qpp::ex	perimenta	al Namespace Reference	119
	6.3.1	Detailed	Description	119
6.4	qpp::in	ternal Nan	mespace Reference	119
	6.4.1	Detailed	Description	120
	6.4.2	Function	Documentation	120
		6.4.2.1	check_cvector()	120
		6.4.2.2	check_dims()	120
		6.4.2.3	check_dims_match_cvect()	121
		6.4.2.4	check_dims_match_mat()	121
		6.4.2.5	check_dims_match_rvect()	121
		6.4.2.6	check_eq_dims()	121

		6.4.2.7	check_matching_sizes()	21
		6.4.2.8	check_no_duplicates()	21
		6.4.2.9	check_nonzero_size()	22
		6.4.2.10	check_perm()	22
		6.4.2.11	check_qubit_cvector()	22
		6.4.2.12	check_qubit_matrix()	22
		6.4.2.13	check_qubit_rvector()	22
		6.4.2.14	check_qubit_vector()	22
		6.4.2.15	check_rvector()	23
		6.4.2.16	check_square_mat()	23
		6.4.2.17	check_subsys_match_dims()	23
		6.4.2.18	check_vector()	23
		6.4.2.19	dirsum2()	23
		6.4.2.20	get_dim_subsys()	23
		6.4.2.21	get_num_subsys()	24
		6.4.2.22	kron2()	24
		6.4.2.23	multiidx2n()	24
		6.4.2.24	n2multiidx()	24
		6.4.2.25	variadic_vector_emplace() [1/2]	24
		6.4.2.26	variadic_vector_emplace() [2/2]	24
6.5	qpp::lit	erals Nam	espace Reference	25
	6.5.1	Function	Documentation	25
		6.5.1.1	operator"""" _bra()	25
		6.5.1.2	operator""""_i()	25
		6.5.1.3	operator"""" _ket()	26
		6.5.1.4	operator"""" _prj()	26

7	Clas	s Docu	mentation	129
	7.1	qpp::Bi	t_circuit Class Reference	129
		7.1.1	Detailed Description	131
		7.1.2	Constructor & Destructor Documentation	131
			7.1.2.1 Bit_circuit()	131
		7.1.3	Member Function Documentation	131
			7.1.3.1 CNOT()	131
			7.1.3.2 Dynamic_bitset()	132
			7.1.3.3 FRED()	132
			7.1.3.4 NOT()	132
			7.1.3.5 reset()	133
			7.1.3.6 SWAP()	133
			7.1.3.7 TOF()	133
			7.1.3.8 X()	134
		7.1.4	Member Data Documentation	134
			7.1.4.1 gate_count	134
	7.2	qpp::C	odes Class Reference	134
		7.2.1	Detailed Description	135
		7.2.2	Member Enumeration Documentation	135
			7.2.2.1 Type	136
		7.2.3	Constructor & Destructor Documentation	136
			7.2.3.1 Codes()	136
			7.2.3.2 ~Codes()	136
		7.2.4	Member Function Documentation	136
			7.2.4.1 codeword()	136
		7.2.5	Friends And Related Function Documentation	137
			7.2.5.1 internal::Singleton < const Codes >	137
	7.3	qpp::ex	cception::CustomException Class Reference	137
		7.3.1	Detailed Description	138
		7.3.2	Constructor & Destructor Documentation	138

CONTENTS xi

		7.3.2.1	CustomException()	. 139
	7.3.3	Member F	Function Documentation	. 139
		7.3.3.1	type_description()	. 139
	7.3.4	Member [Data Documentation	. 139
		7.3.4.1	what	. 139
7.4	qpp::ex	xception::D	imsInvalid Class Reference	. 140
	7.4.1	Detailed [Description	. 141
	7.4.2	Member F	Function Documentation	. 141
		7.4.2.1	Exception()	. 141
		7.4.2.2	type_description()	. 141
7.5	qpp::ex	xception::D	imsMismatchCvector Class Reference	. 142
	7.5.1	Detailed [Description	. 143
	7.5.2	Member F	Function Documentation	. 143
		7.5.2.1	Exception()	. 143
		7.5.2.2	type_description()	. 143
7.6	qpp::ex	xception::D	imsMismatchMatrix Class Reference	. 144
	7.6.1	Detailed [Description	. 145
	7.6.2	Member F	Function Documentation	. 145
		7.6.2.1	Exception()	. 145
		7.6.2.2	type_description()	. 145
7.7	qpp::ex	xception::D	imsMismatchRvector Class Reference	. 146
	7.7.1	Detailed [Description	. 147
	7.7.2	Member F	Function Documentation	. 147
		7.7.2.1	Exception()	. 147
		7.7.2.2	type_description()	. 147
7.8	qpp::ex	xception::D	imsMismatchVector Class Reference	. 148
	7.8.1	Detailed [Description	. 149
	7.8.2	Member F	Function Documentation	. 149
		7.8.2.1	Exception()	. 149
		7.8.2.2	type_description()	. 149

xii CONTENTS

7.9	qpp::ex	cception::DimsNotEqual Class Reference
	7.9.1	Detailed Description
	7.9.2	Member Function Documentation
		7.9.2.1 Exception()
		7.9.2.2 type_description()
7.10	qpp::in	ternal::Display_Impl_ Struct Reference
	7.10.1	Member Function Documentation
		7.10.1.1 display_impl_()
7.11	qpp::ex	cception::Duplicates Class Reference
	7.11.1	Detailed Description
	7.11.2	Member Function Documentation
		7.11.2.1 Exception()
		7.11.2.2 type_description()
7.12	qpp::D	ynamic_bitset Class Reference
	7.12.1	Detailed Description
	7.12.2	Member Typedef Documentation
		7.12.2.1 storage_type
		7.12.2.2 value_type
	7.12.3	Constructor & Destructor Documentation
		7.12.3.1 Dynamic_bitset()
		7.12.3.2 ~Dynamic_bitset()
	7.12.4	Member Function Documentation
		7.12.4.1 all()
		7.12.4.2 any()
		7.12.4.3 count()
		7.12.4.4 data()
		7.12.4.5 display()
		7.12.4.6 flip() [1/2]
		7.12.4.7 flip() [2/2]
		7.12.4.8 get()

CONTENTS xiii

		7.12.4.9 index_()	60
		7.12.4.10 none()	61
		7.12.4.11 offset_()	61
		7.12.4.12 operator"!=()	61
		7.12.4.13 operator-()	62
		7.12.4.14 operator==()	62
		7.12.4.15 rand() [1/2]	62
		7.12.4.16 rand() [2/2]	63
		7.12.4.17 reset() [1/2]	63
		7.12.4.18 reset() [2/2]	63
		7.12.4.19 set() [1/2]	64
		7.12.4.20 set() [2/2]	64
		7.12.4.21 size()	64
		7.12.4.22 storage_size()	64
		7.12.4.23 to_string()	65
	7.12.5	Member Data Documentation	65
		7.12.5.1 N	65
		7.12.5.2 storage_size	65
		7.12.5.3 v	66
7.13	qpp::ex	cception::Exception Class Reference	66
	7.13.1	Detailed Description	68
	7.13.2	Constructor & Destructor Documentation	69
		7.13.2.1 Exception()	69
	7.13.3	Member Function Documentation	69
		7.13.3.1 type_description()	69
		7.13.3.2 what()	70
	7.13.4	Member Data Documentation	70
		7.13.4.1 msg	70
		7.13.4.2 where	70
7.14	qpp::Bi	it_circuit::Gate_count Struct Reference	70

xiv CONTENTS

	7.14.1	Member Data Documentation
		7.14.1.1 CNOT
		7.14.1.2 FRED
		7.14.1.3 NOT
		7.14.1.4 SWAP
		7.14.1.5 TOF
		7.14.1.6 X
7.15	qpp::Ga	ates Class Reference
	7.15.1	Detailed Description
	7.15.2	Constructor & Destructor Documentation
		7.15.2.1 Gates()
		7.15.2.2 ~Gates()
	7.15.3	Member Function Documentation
		7.15.3.1 CTRL()
		7.15.3.2 expandout() [1/3]
		7.15.3.3 expandout() [2/3]
		7.15.3.4 expandout() [3/3]
		7.15.3.5 Fd()
		7.15.3.6 get_name()
		7.15.3.7 ld()
		7.15.3.8 MODMUL()
		7.15.3.9 Rn()
		7.15.3.10 RX()
		7.15.3.11 RY()
		7.15.3.12 RZ()
		7.15.3.13 SWAPd()
		7.15.3.14 Xd()
		7.15.3.15 Zd()
	7.15.4	Friends And Related Function Documentation
		7.15.4.1 internal::Singleton < const Gates >

CONTENTS xv

	7.15.5	Member Data Documentation	33
		7.15.5.1 CNOT	33
		7.15.5.2 CNOTba	33
		7.15.5.3 CZ	33
		7.15.5.4 FRED	33
		7.15.5.5 H	34
		7.15.5.6 ld2	34
		7.15.5.7 S	34
		7.15.5.8 SWAP	34
		7.15.5.9 T	34
		7.15.5.10 TOF	34
		7.15.5.11 X	35
		7.15.5.12 Y	35
		7.15.5.13 Z	35
7.16	qpp::Q0	CircuitDescription::GateStep Struct Reference	35
	7.16.1	Detailed Description	36
	7.16.2	Constructor & Destructor Documentation	36
		7.16.2.1 GateStep() [1/2]	36
		7.16.2.2 GateStep() [2/2]	36
	7.16.3	Member Data Documentation	37
		7.16.3.1 ctrl	37
		7.16.3.2 gate	37
		7.16.3.3 gate_type	37
		7.16.3.4 name	37
		7.16.3.5 step_no	38
		7.16.3.6 target	38
7.17	qpp::ID	isplay Class Reference	38
	7.17.1	Detailed Description	39
	7.17.2	Constructor & Destructor Documentation	39
		7.17.2.1 IDisplay() [1/3]	39

xvi CONTENTS

		7.17.2.2 Display() [2/3]	0
		7.17.2.3 IDisplay() [3/3]	90
		7.17.2.4 ~IDisplay()	90
	7.17.3	Member Function Documentation	90
		7.17.3.1 display()	90
		7.17.3.2 operator=() [1/2]	90
		7.17.3.3 operator=() [2/2])1
	7.17.4	Friends And Related Function Documentation)1
		7.17.4.1 operator<< 19)1
7.18	qpp::Ini	it Class Reference)1
	7.18.1	Detailed Description)2
	7.18.2	Constructor & Destructor Documentation)2
		7.18.2.1 Init())2
		7.18.2.2 ~Init())3
	7.18.3	Friends And Related Function Documentation)3
		7.18.3.1 internal::Singleton < const Init >)3
7.19	qpp::ex	cception::InvalidIterator Class Reference)3
	7.19.1	Detailed Description)4
	7.19.2	Member Function Documentation)4
		7.19.2.1 Exception())4
		7.19.2.2 type_description())5
7.20	qpp::int	ternal::IOManipEigen Class Reference)5
	7.20.1	Constructor & Destructor Documentation)6
		7.20.1.1 IOManipEigen() [1/2])6
		7.20.1.2 IOManipEigen() [2/2])7
	7.20.2	Member Function Documentation)7
		7.20.2.1 display())7
	7.20.3	Member Data Documentation)7
		7.20.3.1 A)7
		7.20.3.2 chop)7

CONTENTS xvii

7.21	qpp::int	ternal::IOManipPointer< PointerType > Class Template Reference	98
	7.21.1	Constructor & Destructor Documentation	99
		7.21.1.1 IOManipPointer() [1/2]	99
		7.21.1.2 IOManipPointer() [2/2]	99
	7.21.2	Member Function Documentation	99
		7.21.2.1 display()	99
		7.21.2.2 operator=()	00
	7.21.3	Member Data Documentation	00
		7.21.3.1 end	00
		7.21.3.2 N __	00
		7.21.3.3 p	00
		7.21.3.4 separator	00
		7.21.3.5 start	00
7.22	qpp::int	ternal::IOManipRange< InputIterator > Class Template Reference	01
	7.22.1	Constructor & Destructor Documentation	02
		7.22.1.1 IOManipRange() [1/2]	02
		7.22.1.2 IOManipRange() [2/2]	02
	7.22.2	Member Function Documentation	02
		7.22.2.1 display()	02
		7.22.2.2 operator=()	03
	7.22.3	Member Data Documentation	03
		7.22.3.1 end	03
		7.22.3.2 first	03
		7.22.3.3 last	03
		7.22.3.4 separator	03
		7.22.3.5 start	03
7.23	qpp::IC	OCircuit Class Reference	04
	7.23.1	Detailed Description	06
	7.23.2	Constructor & Destructor Documentation	06
		7.23.2.1 IQCircuit() [1/2]	06

xviii CONTENTS

	7.23.2.2	10	IQ	Ci	rcu	uit()	[2	2/2	2]															 207
	7.23.2.3	^	\sim	IQ	Cir	cui	t()																	207
7.23.3	Member F	Fu	un	cti	on	Do	ocı	ıme	ent	tat	ior	1												207
	7.23.3.1	d	dis	spl	ay(()																		207
	7.23.3.2	g	ge	t_0	circ	cuit	t_d	es	cri	pti	on	()												 207
	7.23.3.3	g	ge	t_c	dit(()																		208
	7.23.3.4	g	ge	t_c	dits	s()																		208
	7.23.3.5	g	ge	ıt_i	ip()) .																		 208
	7.23.3.6	g	ge	t_i	iter	r()																		209
	7.23.3.7	g	ge	t_i	m_	_ip() .																	 209
	7.23.3.8	g	ge	t_1	me	as	ure	ed() [1/	'2]													209
	7.23.3.9	g	ge	ıt_ı	me	as	ure	ed() [2/	'2]													209
	7.23.3.10) g	ge	t_1	not	t_n	nea	asu	red	d ()) .													210
	7.23.3.11	1 g	ge	t_	pro	bs	()																	210
	7.23.3.12	2 g	ge	t_	psi	()																		210
	7.23.3.13	3 g	ge	t_c	q_i	ip()																		211
	7.23.3.14	4 g	ge	ıt_ı	ref_	_p:	si()																	211
	7.23.3.15	5 g	ge	t_i	rela	ativ	/e_	po	S_	()														 211
	7.23.3.16	3 is	is_	_m	ea	sui	ren	ner	nt_	st	ер	()												 211
	7.23.3.17	7 r	re	set	t()																			212
	7.23.3.18	3 rı	ru	n()																				 212
	7.23.3.19	9 s	se	t_0	dit(()																		212
	7.23.3.20) s	se	t_r	me	as	ure	ed_	_()															 212
7.23.4	Member [Da	at	a [Dod	cur	ne	nta	tio	n														 213
	7.23.4.1	d	dit	:S_																				 213
	7.23.4.2	it	it_	-																				 213
	7.23.4.3	p	pr	ob	s_																			 213
	7.23.4.4	p	ps	i_																				 213
	7.23.4.5	q	qc	:d_																				 213
	7.23.4.6	S	su	bs	ys																			 214

CONTENTS xix

7.24	qpp::is_	_complex< T > Struct Template Reference	14
	7.24.1	Detailed Description	15
7.25	qpp::is_	_complex< std::complex< T $>$ > Struct Template Reference	15
	7.25.1	Detailed Description	16
7.26	qpp::is_	_iterable < T, typename > Struct Template Reference	16
	7.26.1	Detailed Description	17
7.27		_iterable $<$ T, to_void $<$ decltype(std::declval $<$ T $>$ ().begin()), decltype(std::declval $<$ T d()), decltype(*(std::declval $<$ T $>$ ().begin()))> $>$ Struct Template Reference 2	17
	7.27.1	Detailed Description	18
7.28	qpp::is_	_matrix_expression< Derived > Struct Template Reference	18
	7.28.1	Detailed Description	19
7.29	qpp::Q	CircuitDescription::iterator Class Reference	19
	7.29.1	Detailed Description	21
	7.29.2	Member Typedef Documentation	21
		7.29.2.1 difference_type	21
		7.29.2.2 iterator_category	21
		7.29.2.3 pointer	21
		7.29.2.4 reference	21
		7.29.2.5 value_type	21
	7.29.3	Constructor & Destructor Documentation	22
		7.29.3.1 iterator() [1/2]	22
		7.29.3.2 iterator() [2/2]	22
	7.29.4	Member Function Documentation	22
		7.29.4.1 operator"!=()	22
		7.29.4.2 operator*()	22
		7.29.4.3 operator++() [1/2]	23
		7.29.4.4 operator++() [2/2]	23
		7.29.4.5 operator=()	23
		7.29.4.6 operator==()	23
		7.29.4.7 set_()	24
	7.29.5	Friends And Related Function Documentation	24

7.29.5.1 IQCircui	t	224
7.29.6 Member Data Doc	umentation	224
7.29.6.1 elem_		224
7.29.6.2 qcd		224
7.29.6.3 QCircuit	Description	225
7.30 qpp::make_void< Ts > Str	ruct Template Reference	225
7.30.1 Detailed Description	on	225
7.30.2 Member Typedef D	Documentation	225
7.30.2.1 type .		225
7.31 qpp::exception::MatrixMisn	natchSubsys Class Reference	226
7.31.1 Detailed Description	n	227
7.31.2 Member Function	Documentation	227
7.31.2.1 Exception	on()	227
7.31.2.2 type_de	scription()	227
7.32 qpp::exception::MatrixNotC	Cvector Class Reference	228
7.32.1 Detailed Description	n	229
7.32.2 Member Function	Documentation	229
7.32.2.1 Exception	on()	229
7.32.2.2 type_de	scription()	229
7.33 qpp::exception::MatrixNotF	Rvector Class Reference	230
7.33.1 Detailed Description	n	231
7.33.2 Member Function	Documentation	231
7.33.2.1 Exception	on()	231
7.33.2.2 type_de	scription()	231
7.34 qpp::exception::MatrixNotS	Square Class Reference	232
7.34.1 Detailed Description	n	233
7.34.2 Member Function	Documentation	233
7.34.2.1 Exception	on()	233
7.34.2.2 type_de	scription()	233
7.35 qpp::exception::MatrixNotS	SquareNorCvector Class Reference	234

CONTENTS xxi

	7.35.1	Detailed Description	35
	7.35.2	Member Function Documentation	35
		7.35.2.1 Exception()	35
		7.35.2.2 type_description()	35
7.36	qpp::ex	ception::MatrixNotSquareNorRvector Class Reference	36
	7.36.1	Detailed Description	37
	7.36.2	Member Function Documentation	37
		7.36.2.1 Exception()	37
		7.36.2.2 type_description()	37
7.37	qpp::ex	ception::MatrixNotSquareNorVector Class Reference	38
	7.37.1	Detailed Description	39
	7.37.2	Member Function Documentation	39
		7.37.2.1 Exception()	39
		7.37.2.2 type_description()	39
7.38	qpp::ex	ception::MatrixNotVector Class Reference	1 0
	7.38.1	Detailed Description	11
	7.38.2	Member Function Documentation	11
		7.38.2.1 Exception()	11
		7.38.2.2 type_description()	11
7.39	qpp::Q	CircuitDescription::MeasureStep Struct Reference	12
	7.39.1	Detailed Description	12
	7.39.2	Constructor & Destructor Documentation	13
		7.39.2.1 MeasureStep() [1/2]	13
		7.39.2.2 MeasureStep() [2/2]	13
	7.39.3	Member Data Documentation	13
		7.39.3.1 c_reg	13
		7.39.3.2 mats	14
		7.39.3.3 measurement_type	14
		7.39.3.4 name	14
		7.39.3.5 step_no	14

xxii CONTENTS

		7.39.3.6	ta	arget							 	244						
7.40	qpp::ex	ception::N	NoC	Code	word	Class	s Ref	erer	ice		 		 	 	 	 	 	245
	7.40.1	Detailed	l De	escrip	otion						 		 	 	 	 	 	246
	7.40.2	Member	Fu	ınctio	n Doo	cume	ntatio	on			 	246						
		7.40.2.1	Е	xcep	otion()						 	246						
		7.40.2.2	t ty	ype_d	descri	iption	1() .				 	246						
7.41	qpp::No	oiseBase<	< T	Γ > C	Class T	Temp	olate	Refe	eren	ce .	 	247						
	7.41.1	Detailed	l De	escrip	otion						 	248						
	7.41.2	Member	Тур	pede	f Doc	umer	ntatio	n .			 		 	 	 	 	 	248
		7.41.2.1	n	oise_	_type						 	248						
	7.41.3	Construc	ctor	r & D	estruc	ctor E	Oocur	men	tatio	n	 	249						
		7.41.3.1	N	loise	Base(() [1/	/2].				 	249						
		7.41.3.2	. N	loise	Base(() [2/	/2].				 	249						
		7.41.3.3	~	~Nois	seBas	se()					 	250						
	7.41.4	Member	Fu	ınctio	n Doo	cume	entatio	on			 	250						
		7.41.4.1	C	ompi	ute_p	robs_	_() .				 	250						
		7.41.4.2	! C	ompi	ute_st	tate_	.()				 	250						
		7.41.4.3	g	et_d	()						 	251						
		7.41.4.4	g	et_K	.s()						 	251						
		7.41.4.5	g	et_la	ıst_id	x() .					 	251						
		7.41.4.6	g	et_la	ıst_K() .					 	251						
		7.41.4.7	g	et_la	ist_p() .					 	252						
		7.41.4.8	g	et_p	robs())					 	252						
		7.41.4.9	0	pera	tor()()	[1/2	2] .				 		 	 	 	 	 	252
		7.41.4.10	0 о	pera	tor()()	[2/2	2] .				 	253						
	7.41.5	Member	⁻ Da	ata D	ocum	entat	ion .				 	253						
		7.41.5.1	d	L .							 	253						
		7.41.5.2	g	ener	ated_						 		 	 	 	 	 	253
		7.41.5.3	i_								 	253						
		7.41.5.4	K	(s							 		 	 	 	 	 	254

CONTENTS xxiii

		7.41.5.5 probs	254
7.42	qpp::No	piseType Class Reference	254
	7.42.1	Detailed Description	254
7.43	qpp::ex	ception::NotBipartite Class Reference	255
	7.43.1	Detailed Description	256
	7.43.2	Member Function Documentation	256
		7.43.2.1 Exception()	256
		7.43.2.2 type_description()	256
7.44	qpp::ex	ception::NotImplemented Class Reference	257
	7.44.1	Detailed Description	258
	7.44.2	Member Function Documentation	258
		7.44.2.1 Exception()	258
		7.44.2.2 type_description()	258
7.45	qpp::ex	ception::NotQubitCvector Class Reference	259
	7.45.1	Detailed Description	260
	7.45.2	Member Function Documentation	260
		7.45.2.1 Exception()	260
		7.45.2.2 type_description()	260
7.46	qpp::ex	ception::NotQubitMatrix Class Reference	261
	7.46.1	Detailed Description	262
	7.46.2	Member Function Documentation	262
		7.46.2.1 Exception()	262
		7.46.2.2 type_description()	262
7.47	qpp::ex	ception::NotQubitRvector Class Reference	263
	7.47.1	Detailed Description	264
	7.47.2	Member Function Documentation	264
		7.47.2.1 Exception()	264
		7.47.2.2 type_description()	264
7.48	qpp::ex	ception::NotQubitSubsys Class Reference	265
	7.48.1	Detailed Description	266

xxiv CONTENTS

	7.48.2	Member F	unction Doc	umentatio	on		 	 	 	 	. 266
		7.48.2.1	Exception()				 	 	 	 	. 266
		7.48.2.2	type_descrip	otion() .			 	 	 	 	. 266
7.49	qpp::ex	ception::N	otQubitVecto	r Class R	eference	e	 	 	 	 	. 267
	7.49.1	Detailed [Description				 	 	 	 	. 268
	7.49.2	Member F	Function Doc	umentatio	on		 	 	 	 	. 268
		7.49.2.1	Exception()				 	 	 	 	. 268
		7.49.2.2	type_descrip	otion() .			 	 	 	 	. 268
7.50	qpp::ex	ception::O	utOfRange C	lass Refe	erence		 	 	 	 	. 269
	7.50.1	Detailed [Description				 	 	 	 	. 270
	7.50.2	Member F	Function Doc	umentatio	on		 	 	 	 	. 270
		7.50.2.1	Exception()				 	 	 	 	. 270
		7.50.2.2	type_descrip	otion() .			 	 	 	 	. 270
7.51	qpp::ex	ception::Pe	ermInvalid Cl	ass Refer	ence.		 	 	 	 	. 271
	7.51.1	Detailed [Description				 	 	 	 	. 272
	7.51.2	Member F	Function Doc	umentatio	on		 	 	 	 	. 272
		7.51.2.1	Exception()				 	 	 	 	. 272
		7.51.2.2	type_descrip	otion() .			 	 	 	 	. 272
7.52	qpp::ex	ception::Pe	ermMismatch	ıDims Cla	ıss Refe	rence	 	 	 	 	. 273
	7.52.1	Detailed [Description				 	 	 	 	. 274
	7.52.2	Member F	Function Doc	umentatio	on		 	 	 	 	. 274
		7.52.2.1	Exception()				 	 	 	 	. 274
		7.52.2.2	type_descrip	otion() .			 	 	 	 	. 274
7.53	qpp::Q	Circuit Clas	ss Reference				 	 	 	 	. 275
	7.53.1	Detailed [Description				 	 	 	 	. 276
	7.53.2	Member F	Function Doc	umentatio	on		 	 	 	 	. 276
		7.53.2.1	IQCircuit() [1/2]			 	 	 	 	. 276
		7.53.2.2	IQCircuit() [2/2]			 	 	 	 	. 276
		7.53.2.3	run()				 	 	 	 	. 277
7.54	qpp::Q	CircuitDesc	cription Class	Reference	ce		 	 	 	 	. 277

CONTENTS xxv

7.54.1	Detailed Description	31
7.54.2	Member Typedef Documentation	31
	7.54.2.1 const_iterator	31
7.54.3	Member Enumeration Documentation	31
	7.54.3.1 GateType	31
	7.54.3.2 MeasureType	32
7.54.4	Constructor & Destructor Documentation	32
	7.54.4.1 QCircuitDescription()	32
	7.54.4.2 ~QCircuitDescription()	33
7.54.5	Member Function Documentation	33
	7.54.5.1 _to_JSON()	33
	7.54.5.2 begin() [1/2]	33
	7.54.5.3 begin() [2/2]	34
	7.54.5.4 cbegin()	34
	7.54.5.5 cCTRL() [1/4]	34
	7.54.5.6 cCTRL() [2/4]	35
	7.54.5.7 cCTRL() [3/4]	35
	7.54.5.8 cCTRL() [4/4]	35
	7.54.5.9 cCTRL_custom()	36
	7.54.5.10 cend()	36
	7.54.5.11 CTRL() [1/4]	37
	7.54.5.12 CTRL() [2/4]	37
	7.54.5.13 CTRL() [3/4]	38
	7.54.5.14 CTRL() [4/4]	38
	7.54.5.15 CTRL_custom()	39
	7.54.5.16 display()	39
	7.54.5.17 end() [1/2]	90
	7.54.5.18 end() [2/2]	90
	7.54.5.19 gate() [1/3]	90
	7.54.5.20 gate() [2/3]	3 0

xxvi CONTENTS

	7.54.5.21 gate() [3/3]	291
	7.54.5.22 gate_custom()	291
	7.54.5.23 gate_fan() [1/2]	292
	7.54.5.24 gate_fan() [2/2]	292
	7.54.5.25 get_d()	293
	7.54.5.26 get_gate_count()	293
	7.54.5.27 get_gates()	293
	7.54.5.28 get_measured() [1/2]	293
	7.54.5.29 get_measured() [2/2]	294
	7.54.5.30 get_measurement_count()	294
	7.54.5.31 get_measurement_steps()	294
	7.54.5.32 get_measurements()	295
	7.54.5.33 get_name()	295
	7.54.5.34 get_nc()	295
	7.54.5.35 get_non_measured()	295
	7.54.5.36 get_nq()	296
	7.54.5.37 get_steps_count()	296
	7.54.5.38 measureV() [1/2]	296
	7.54.5.39 measureV() [2/2]	297
	7.54.5.40 measureZ()	297
	7.54.5.41 QFT()	297
	7.54.5.42 TFQ()	298
	7.54.5.43 to_JSON()	298
7.54.6	Friends And Related Function Documentation	298
	7.54.6.1 operator<< [1/4]	298
	7.54.6.2 operator<< [2/4]	299
	7.54.6.3 operator<< [3/4]	299
	7.54.6.4 operator<< [4/4]	300
7.54.7	Member Data Documentation	300
	7.54.7.1 d	300

CONTENTS xxvii

		7.54.7.2	gates				 	 	 	 		300
		7.54.7.3	measured_				 	 	 	 		300
		7.54.7.4	measureme	nt_steps_			 	 	 	 		301
		7.54.7.5	measureme	nts			 	 	 	 		301
		7.54.7.6	name				 	 	 	 		301
		7.54.7.7	nc				 	 	 	 		301
		7.54.7.8	nq				 	 	 	 		301
		7.54.7.9	steps_cnt_				 	 	 	 		301
7.55	qpp::Q	ubitAmplitu	ıdeDampingl	Noise Class	s Referer	nce .	 	 	 	 		302
	7.55.1	Detailed I	Description				 	 	 	 		303
	7.55.2	Construct	or & Destruc	tor Docum	entation .		 	 	 	 		303
		7.55.2.1	QubitAmplit	udeDampir	ngNoise())	 	 	 	 		303
7.56	qpp::Q	ubitBitFlip N	Noise Class F	Reference			 	 	 	 		303
	7.56.1	Detailed I	Description				 	 	 	 		304
	7.56.2	Construct	or & Destruc	tor Docum	entation .		 	 	 	 		304
		7.56.2.1	QubitBitFlip	Noise()			 	 	 	 		304
7.57	qpp::Qı	ubitBitPhas	seFlipNoise (Class Refe	rence		 	 	 	 		305
	7.57.1	Detailed I	Description				 	 	 	 		306
	7.57.2	Construct	or & Destruc	tor Docum	entation .		 	 	 	 		306
		7.57.2.1	QubitBitPha	ıseFlipNois	se()		 	 	 	 		306
7.58	qpp::Qı	ubitDepola	rizingNoise (Class Refe	rence		 	 	 	 		306
	7.58.1	Detailed I	Description				 	 	 	 		307
	7.58.2	Construct	or & Destruc	tor Docum	entation .		 	 	 	 		307
		7.58.2.1	QubitDepola	arizingNois	e()		 	 	 	 		307
7.59	qpp::Qı	ubitPhase[DampingNois	se Class Re	eference		 	 	 	 		308
	7.59.1	Detailed I	Description				 	 	 	 		309
	7.59.2	Construct	or & Destruc	tor Docum	entation		 	 	 	 		309
		7.59.2.1	QubitPhase	DampingN	loise() .		 	 	 	 		309
7.60	qpp::Q	ubitPhaseF	FlipNoise Cla	ıss Referer	nce		 	 	 	 		309
	7.60.1	Detailed I	Description				 	 	 	 		310

xxviii CONTENTS

	7.60.2	Constructor & Destructor Documentation
		7.60.2.1 QubitPhaseFlipNoise()
7.61	qpp::ex	cception::QuditAlreadyMeasured Class Reference
	7.61.1	Detailed Description
	7.61.2	Member Function Documentation
		7.61.2.1 Exception()
		7.61.2.2 type_description()
7.62	qpp::Q	uditDepolarizingNoise Class Reference
	7.62.1	Detailed Description
	7.62.2	Constructor & Destructor Documentation
		7.62.2.1 QuditDepolarizingNoise()
	7.62.3	Member Function Documentation
		7.62.3.1 fill_Ks_()
		7.62.3.2 fill_probs_()
	7.62.4	Member Data Documentation
		7.62.4.1 d
7.63	qpp::Ra	andomDevices Class Reference
	7.63.1	Detailed Description
	7.63.2	Constructor & Destructor Documentation
		7.63.2.1 RandomDevices()
		7.63.2.2 ~RandomDevices()
	7.63.3	Member Function Documentation
		7.63.3.1 get_prng()
		7.63.3.2 load()
		7.63.3.3 save()
	7.63.4	Friends And Related Function Documentation
		7.63.4.1 internal::Singleton < RandomDevices >
	7.63.5	Member Data Documentation
		7.63.5.1 prng
		7.63.5.2 rd

CONTENTS xxix

7.64	qpp::in	ternal::Singleton < T > Class Template Reference	319
	7.64.1	Detailed Description	320
	7.64.2	Constructor & Destructor Documentation	320
		7.64.2.1 Singleton() [1/2]	321
		7.64.2.2 Singleton() [2/2]	321
		7.64.2.3 ~Singleton()	321
	7.64.3	Member Function Documentation	321
		7.64.3.1 get_instance()	321
		7.64.3.2 get_thread_local_instance()	321
		7.64.3.3 operator=()	321
7.65	qpp::ex	cception::SizeMismatch Class Reference	322
	7.65.1	Detailed Description	323
	7.65.2	Member Function Documentation	323
		7.65.2.1 Exception()	323
		7.65.2.2 type_description()	323
7.66	qpp::No	piseType::StateDependent Class Reference	324
7.66		Detailed Description	
	7.66.1		324
	7.66.1 qpp::No	Detailed Description	324 324
7.67	7.66.1 qpp::No 7.67.1	Detailed Description	324 324 324
7.67	7.66.1 qpp::No 7.67.1 qpp::St	Detailed Description	324 324 324 324
7.67	7.66.1 qpp::No 7.67.1 qpp::St	Detailed Description	324 324 324 324 326
7.67	7.66.1 qpp::No 7.67.1 qpp::St	Detailed Description	324 324 324 324 326 327
7.67	7.66.1 qpp::No 7.67.1 qpp::St	Detailed Description DiseType::StateIndependent Class Reference Detailed Description ates Class Reference Detailed Description Constructor & Destructor Documentation	324 324 324 326 327 327
7.67	7.66.1 qpp::No 7.67.1 qpp::St 7.68.1 7.68.2	Detailed Description Detailed Description Detailed Description Detailed Description Detailed Description Detailed Description Constructor & Destructor Documentation 7.68.2.1 States()	324 324 324 326 327 327
7.67	7.66.1 qpp::No 7.67.1 qpp::St 7.68.1 7.68.2	Detailed Description Detailed Description Detailed Description Detailed Description Detailed Description Constructor & Destructor Documentation 7.68.2.1 States()	324 324 324 326 327 327 327
7.67	7.66.1 qpp::No 7.67.1 qpp::St 7.68.1 7.68.2	Detailed Description DiseType::StateIndependent Class Reference Detailed Description ates Class Reference Detailed Description Constructor & Destructor Documentation 7.68.2.1 States() 7.68.2.2 ~States() Member Function Documentation	324 324 324 326 327 327 327
7.67	7.66.1 qpp::No 7.67.1 qpp::St 7.68.1 7.68.2	Detailed Description DiseType::StateIndependent Class Reference Detailed Description ates Class Reference Detailed Description Constructor & Destructor Documentation 7.68.2.1 States() 7.68.2.2 ~States() Member Function Documentation 7.68.3.1 jn()	324 324 324 326 327 327 327 327
7.67	7.66.1 qpp::No 7.67.1 qpp::St 7.68.1 7.68.2	Detailed Description DiseType::StateIndependent Class Reference Detailed Description ates Class Reference Detailed Description Constructor & Destructor Documentation 7.68.2.1 States() 7.68.2.2 ~States() Member Function Documentation 7.68.3.1 jn() 7.68.3.2 mes()	324 324 324 326 327 327 327 327 327

		7.68.3.6 zero()
	7.68.4	Friends And Related Function Documentation
		7.68.4.1 internal::Singleton < const States >
	7.68.5	Member Data Documentation
		7.68.5.1 b00
		7.68.5.2 b01
		7.68.5.3 b10
		7.68.5.4 b11
		7.68.5.5 GHZ
		7.68.5.6 pb00
		7.68.5.7 pb01
		7.68.5.8 pb10
		7.68.5.9 pb11
		7.68.5.10 pGHZ
		7.68.5.11 pW
		7.68.5.12 px0
		7.68.5.13 px1
		7.68.5.14 py0
		7.68.5.15 py1
		7.68.5.16 pz0
		7.68.5.17 pz1
		7.68.5.18 W
		7.68.5.19 x0
		7.68.5.20 x1
		7.68.5.21 y0
		7.68.5.22 y1
		7.68.5.23 z0
		7.68.5.24 z1
7.69	qpp::ex	cception::SubsysMismatchDims Class Reference
	7.69.1	Detailed Description

CONTENTS xxxi

	7.69.2	Member Function Documentation	35
		7.69.2.1 Exception()	35
		7.69.2.2 type_description()	35
7.70	qpp::Ti	mer < T, CLOCK_T > Class Template Reference	36
	7.70.1	Detailed Description	37
	7.70.2	Constructor & Destructor Documentation	37
		7.70.2.1 Timer() [1/3]	37
		7.70.2.2 Timer() [2/3]	38
		7.70.2.3 Timer() [3/3]	38
		7.70.2.4 ~Timer()	38
	7.70.3	Member Function Documentation	38
		7.70.3.1 display()	38
		7.70.3.2 get_duration()	39
		7.70.3.3 operator=() [1/2]	39
		7.70.3.4 operator=() [2/2]	39
		7.70.3.5 tic()	1 0
		7.70.3.6 tics()	1 0
		7.70.3.7 toc()	10
	7.70.4	Member Data Documentation	1 0
		7.70.4.1 end	1 0
		7.70.4.2 start	11
7.71	qpp::ex	cception::TypeMismatch Class Reference	11
	7.71.1	Detailed Description	12
	7.71.2	Member Function Documentation	12
		7.71.2.1 Exception()	12
		7.71.2.2 type_description()	13
7.72	qpp::ex	cception::UndefinedType Class Reference	13
	7.72.1	Detailed Description	14
	7.72.2	Member Function Documentation	14
		7.72.2.1 Exception()	14

xxxii CONTENTS

	7.72.2.2 type_description()
7.73 qpp::ex	xception::Unknown Class Reference
7.73.1	Detailed Description
7.73.2	Member Function Documentation
	7.73.2.1 Exception()
	7.73.2.2 type_description()
7.74 qpp::Q	CircuitDescription::iterator::value_type_ Struct Reference
7.74.1	Constructor & Destructor Documentation
	7.74.1.1 value_type_() [1/2]
	7.74.1.2 value_type_() [2/2]
7.74.2	Member Function Documentation
	7.74.2.1 display()
	7.74.2.2 operator=()
7.74.3	Member Data Documentation
	7.74.3.1 ip
	7.74.3.2 is_measurement
	7.74.3.3 m_ip
	7.74.3.4 q_ip
	7.74.3.5 value_type_qcd
7.75 qpp::ex	xception::ZeroSize Class Reference
7.75.1	Detailed Description
7.75.2	Member Function Documentation
	7.75.2.1 Exception()
	7.75.2.2 type_description()

CONTENTS xxxiii

8	File I	Documentation	353
	8.1	classes/circuits.h File Reference	353
		8.1.1 Detailed Description	354
	8.2	classes/codes.h File Reference	354
		8.2.1 Detailed Description	354
	8.3	classes/exception.h File Reference	355
		8.3.1 Detailed Description	357
	8.4	classes/gates.h File Reference	357
		8.4.1 Detailed Description	357
	8.5	classes/idisplay.h File Reference	358
		8.5.1 Detailed Description	358
	8.6	classes/init.h File Reference	358
		8.6.1 Detailed Description	359
	8.7	classes/noise.h File Reference	359
		8.7.1 Detailed Description	360
	8.8	classes/random_devices.h File Reference	360
		8.8.1 Detailed Description	360
	8.9	classes/reversible.h File Reference	361
		8.9.1 Detailed Description	361
	8.10	classes/states.h File Reference	361
		8.10.1 Detailed Description	362
	8.11	classes/timer.h File Reference	362
		8.11.1 Detailed Description	363
	8.12	constants.h File Reference	363
		8.12.1 Detailed Description	364
	8.13	entanglement.h File Reference	364
		8.13.1 Detailed Description	366
	8.14	entropies.h File Reference	366
		8.14.1 Detailed Description	367
	8.15	experimental/experimental.h File Reference	367

	8.15.1 Detailed Description	367
8.16	functions.h File Reference	367
	8.16.1 Detailed Description	372
8.17	input_output.h File Reference	372
	8.17.1 Detailed Description	373
8.18	instruments.h File Reference	373
	8.18.1 Detailed Description	374
8.19	internal/classes/iomanip.h File Reference	374
	8.19.1 Detailed Description	375
8.20	internal/classes/singleton.h File Reference	375
	8.20.1 Detailed Description	376
8.21	internal/util.h File Reference	376
	8.21.1 Detailed Description	377
8.22	MATLAB/matlab.h File Reference	378
	8.22.1 Detailed Description	378
8.23	number_theory.h File Reference	378
	8.23.1 Detailed Description	380
8.24	operations.h File Reference	380
	8.24.1 Detailed Description	382
8.25	qpp.h File Reference	382
	8.25.1 Detailed Description	384
	8.25.2 Macro Definition Documentation	384
	8.25.2.1 QPP_UNUSED	384
8.26	random.h File Reference	384
	8.26.1 Detailed Description	385
8.27	statistics.h File Reference	386
	8.27.1 Detailed Description	387
8.28	traits.h File Reference	387
	8.28.1 Detailed Description	388
8.29	types.h File Reference	388
	8.29.1 Detailed Description	389
8.30	/Users/vlad/qpp/README.md File Reference	389

Index

391

Chapter 1

Quantum++

Version 1.1 - 26 November 2018

Build status:

Chat (questions/issues)

About

Quantum++ is a modern C++11 general purpose quantum computing library, composed solely of template header files. Quantum++ is written in standard C++11 and has very low external dependencies, using only the Eigen 3 linear algebra header-only template library and, if available, the OpenMP multi-processing library.

Quantum++ is not restricted to qubit systems or specific quantum information processing tasks, being capable of simulating arbitrary quantum processes. The main design factors taken in consideration were the ease of use, high portability, and high performance. The library's simulation capabilities are only restricted by the amount of available physical memory. On a typical machine (Intel i5 8Gb RAM) Quantum++ can successfully simulate the evolution of 25 qubits in a pure state or of 12 qubits in a mixed state reasonably fast.

To report any bugs or ask for additional features/enhancements, please submit an issue with an appropriate label.

If you are interesting in contributing to this project, feel free to contact me. Alternatively, create a custom branch, add your contribution, then finally create a pull request. If I accept the pull request, I will merge your custom branch with the latest development branch. The latter will eventually be merged into a future release version. To contribute, you need to have a solid knowledge of C++ (preferably C++11), including templates and the standard library, a basic knowledge of quantum computing and linear algebra, and working experience with Eigen 3.

For additional Eigen 3 documentation see http://eigen.tuxfamily.org/dox/. For a simple Eigen 3 quick ASCII reference see http://eigen.tuxfamily.org/dox/AsciiQuickReference.txt.

Copyright (c) 2013 - 2019 Vlad Gheorghiu, vgheorgh AT gmail DOT com.

License

Quantum++ is distributed under the MIT license. Please see the LICENSE file for more details.

Installation instructions and further documentation

Please see the installation guide https://github.com/vsoftco/qpp/blob/master/INSTALL.md "`INSTALL.md`" and the comprehensive Wiki for further documentation and detailed examples.

The official API documentation is available in PDF and HTML formats in the doc folder.

2 Quantum++

Chapter 2

Namespace Index

2.1 Namespace List

Here is a list of all namespaces with brief descriptions:

qpp
Quantum++ main namespace
qpp::exception
Quantum++ exception hierarchy namespace
qpp::experimental
Experimental/test functions/classes, do not use or modify
qpp::internal
Internal utility functions, do not use them directly or modify them
qpp::literals

4 Namespace Index

Chapter 3

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

qpp::internal::Display_Impl
qpp::internal::IOManipEigen
std::exception
qpp::exception::Exception
qpp::exception::CustomException
qpp::exception::DimsInvalid
qpp::exception::DimsMismatchCvector
qpp::exception::DimsMismatchMatrix
app::exception::DimsMismatchRvector
app::exception::DimsMismatchVector
app::exception::DimsNotEqual
qpp::exception::Duplicates
qpp::exception::InvalidIterator
qpp::exception::MatrixMismatchSubsys
qpp::exception::MatrixNotCvector
qpp::exception::MatrixNotRvector
qpp::exception::MatrixNotSquare
qpp::exception::MatrixNotSquareNorCvector
qpp::exception::MatrixNotSquareNorRvector
qpp::exception::MatrixNotSquareNorVector
qpp::exception::MatrixNotVector
qpp::exception::NoCodeword
qpp::exception::NotBipartite
qpp::exception::NotImplemented
qpp::exception::NotQubitCvector
qpp::exception::NotQubitMatrix
qpp::exception::NotQubitRvector
qpp::exception::NotQubitSubsys
qpp::exception::NotQubitVector
qpp::exception::OutOfRange
qpp::exception::PermInvalid
qpp::exception::PermMismatchDims
qpp::exception::QuditAlreadyMeasured
qpp::exception::SizeMismatch
qpp::exception::SubsysMismatchDims

6 Hierarchical Index

qpp::exception::TypeMismatch	341
qpp::exception::UndefinedType	
qpp::exception::Unknown	
qpp::exception::ZeroSize	350
false_type	
$qpp :: is_complex < T > \ \ \ldots \ldots \ldots \ldots \ldots \ldots \ldots \ldots \ldots$	214
qpp::is_iterable < T, typename >	216
qpp::Bit_circuit::Gate_count	. 170
qpp::QCircuitDescription::GateStep	. 185
qpp::IDisplay	. 188
qpp::Dynamic_bitset	155
app::Bit circuit	129
gpp::internal::IOManipEigen	195
qpp::internal::IOManipPointer< PointerType >	
qpp::internal::IOManipRange< InputIterator >	
gpp::IQCircuit	
qpp::QCircuit	
qpp::QCircuitDescription	
qpp::QCircuitDescription::iterator::value_type	
qpp::Timer< T, CLOCK_T >	
is base of	
app::is_matrix_expression< Derived >	210
qpp::QCircuitDescription::iterator	
qpp::make_void< Ts >	
qpp::QCircuitDescription::MeasureStep	
qpp::NoiseBase< T >	
qpp::NoiseBase < NoiseType::StateDependent >	
qpp::QubitAmplitudeDampingNoise	
qpp::QubitPhaseDampingNoise	
${\tt qpp::NoiseBase} < {\tt NoiseType::StateIndependent} > \dots $. 247
qpp::QubitBitFlipNoise	303
qpp::QubitBitPhaseFlipNoise	305
qpp::QubitDepolarizingNoise	306
qpp::QubitPhaseFlipNoise	
qpp::QuditDepolarizingNoise	313
qpp::NoiseType	. 254
qpp::internal::Singleton< T >	. 319
qpp::internal::Singleton < const Codes >	. 319
qpp::Codes	134
qpp::internal::Singleton < const Gates >	
qpp::Gates	
" ·	
qpp::internal::Singleton < const Init >	
qpp::Init	191
$qpp::internal::Singleton\ldots\ldots\ldots\ldots\ldots\ldots\ldots\ldots\ldots\ldots$. 319
qpp::States	324
app::internal::Singleton< RandomDevices >	319
qpp::RandomDevices	
" ·	
qpp::NoiseType::StateDependent	
qpp::NoiseType::StateIndependent	. 324
true_type	015
qpp::is_complex < std::complex < T >>	
<pre>qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval<</pre>	
/().enu()), ueunype(*(siuueuvai< 1 /().beylin()))/ / · · · · · · · · · · · · · · · · ·	21/

Chapter 4

Class Index

4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

qpp::Bit_circuit	
Classical reversible circuit simulator	129
qpp::Codes	
Const Singleton class that defines quantum error correcting codes	134
qpp::exception::CustomException	
Custom exception	137
qpp::exception::DimsInvalid	
Invalid dimension(s) exception	140
qpp::exception::DimsMismatchCvector	
Dimension(s) mismatch column vector size exception	142
qpp::exception::DimsMismatchMatrix	
Dimension(s) mismatch matrix size exception	144
qpp::exception::DimsMismatchRvector	
Dimension(s) mismatch row vector size exception	146
qpp::exception::DimsMismatchVector	
Dimension(s) mismatch vector size exception	148
qpp::exception::DimsNotEqual	
Dimensions not equal exception	150
qpp::internal::Display_Impl	152
qpp::exception::Duplicates	
-, (- 9 , ,	153
qpp::Dynamic_bitset	
Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std←	
,	155
qpp::exception::Exception	
	166
	170
qpp::Gates	
Const Singleton class that implements most commonly used gates	172
qpp::QCircuitDescription::GateStep	
One step consisting only of gates/operators in the circuit	185
qpp::IDisplay	
Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream&	& os) cons
188	
qpp::Init	
Const Singleton class that performs additional initializations/cleanups	191

8 Class Index

qpp::exception::InvalidIterator	
Invalid iterator	193
qpp::internal::IOManipEigen	195
qpp::internal::IOManipPointer< PointerType >	198
qpp::internal::IOManipRange< InputIterator >	201
qpp::IQCircuit	
Quantum circuit simulator abstract class	204
qpp::is_complex < T >	
Checks whether the type is a complex type	214
qpp::is_complex< std::complex< T > >	
Checks whether the type is a complex number type, specialization for complex types	215
qpp::is_iterable< T, typename >	
Checks whether T is compatible with an STL-like iterable container	216
qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval< T >().end()), decltype(std::de	
Checks whether T is compatible with an STL-like iterable container, specialization for STL-like	conyper*(stadecivar
iterable containers	217
	217
qpp::is_matrix_expression< Derived >	010
Checks whether the type is an Eigen matrix expression	210
qpp::QCircuitDescription::iterator	040
Quantum circuit description bound-checking (safe) iterator	219
qpp::make_void< Ts >	
Helper for qpp::to_void<> alias template	225
qpp::exception::MatrixMismatchSubsys	
Matrix mismatch subsystems exception	226
qpp::exception::MatrixNotCvector	
Matrix is not a column vector exception	228
qpp::exception::MatrixNotRvector	
Matrix is not a row vector exception	230
qpp::exception::MatrixNotSquare	
Matrix is not square exception	232
qpp::exception::MatrixNotSquareNorCvector	
Matrix is not square nor column vector exception	234
qpp::exception::MatrixNotSquareNorRvector	
Matrix is not square nor row vector exception	236
qpp::exception::MatrixNotSquareNorVector	
Matrix is not square nor vector exception	238
qpp::exception::MatrixNotVector	
Matrix is not a vector exception	240
qpp::QCircuitDescription::MeasureStep	
One step consisting only of measurements in the circuit	242
qpp::exception::NoCodeword	
Codeword does not exist exception	245
qpp::NoiseBase< T >	
	247
qpp::NoiseType	217
Contains template tags used to specify the noise type	25/
qpp::exception::NotBipartite	204
	255
·	200
qpp::exception::NotImplemented	0.67
, ,	257
qpp::exception::NotQubitCvector	050
·	259
qpp::exception::NotQubitMatrix	004
'	261
qpp::exception::NotQubitRvector	000
Row vector is not 1 x 2 exception	263
qpp::exception::NotQubitSubsys	
Subsystems are not qubits exception	265

4.1 Class List

qpp::exception::NotQubitVector	
Vector is not 2 x 1 nor 1 x 2 exception	267
qpp::exception::OutOfRange	
Argument out of range exception	269
qpp::exception::PermInvalid	
Invalid permutation exception	271
qpp::exception::PermMismatchDims	
Permutation mismatch dimensions exception	273
qpp::QCircuit	
Quantum circuit simulator class	275
qpp::QCircuitDescription	
Quantum circuit description class	277
qpp::QubitAmplitudeDampingNoise	
Qubit amplitude damping noise, as described in Nielsen and Chuang	302
qpp::QubitBitFlipNoise	
Qubit bit flip noise	303
qpp::QubitBitPhaseFlipNoise	
Qubit bit-phase flip (dephasing) noise	305
qpp::QubitDepolarizingNoise	
Qubit depolarizing noise	306
qpp::QubitPhaseDampingNoise	
Qubit phase damping noise, as described in Nielsen and Chuang	308
qpp::QubitPhaseFlipNoise	
Qubit phase flip (dephasing) noise	309
qpp::exception::QuditAlreadyMeasured	
Qudit was already measured exception	311
qpp::QuditDepolarizingNoise	
Qudit depolarizing noise	313
qpp::RandomDevices	
Singleton class that manages the source of randomness in the library	316
qpp::internal::Singleton< T >	
Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously	
recurring template pattern)	319
qpp::exception::SizeMismatch	
Size mismatch exception	322
qpp::NoiseType::StateDependent	
Template tag, used whenever the noise is state-dependent	324
qpp::NoiseType::StateIndependent	
Template tag, used whenever the noise is state-independent	324
qpp::States	004
Const Singleton class that implements most commonly used states	324
qpp::exception::SubsysMismatchDims	004
Subsystems mismatch dimensions exception	334
qpp::Timer< T, CLOCK_T >	
Chronometer	336
qpp::exception::TypeMismatch	
Type mismatch exception	341
qpp::exception::UndefinedType	
Not defined for this type exception	343
qpp::exception::Unknown	6.1-
Unknown exception	345
qpp::QCircuitDescription::iterator::value_type	347
qpp::exception::ZeroSize	
Object has zero size exception	350

10 Class Index

Chapter 5

File Index

5.1 File List

Here is a list of all files with brief descriptions:

constants.h	
Constants	63
entanglement.h	
Entanglement functions	64
entropies.h	
Entropy functions	66
functions.h	
Generic quantum computing functions	67
input_output.h	
Input/output functions	72
instruments.h	
Measurement functions	73
number_theory.h	٠,
Number theory functions	/と
operations.h	۰,
Quantum operation functions	5(
qpp.h Quantum++ main header file, includes all other necessary headers	or
random.h	04
Randomness-related functions	Q,
statistics.h	٥-
Statistics functions	86
traits.h	
Type traits	87
types.h	•
Type aliases	88
classes/circuits.h	
Support for qudit quantum circuits	53
classes/codes.h	
Quantum error correcting codes	54
classes/exception.h	
Exceptions	55
classes/gates.h	
Quantum gates	57
classes/idisplay.h	
Display interface via the non-virtual interface (NVI)	58

12 File Index

asses/init.h	
Initialization	358
asses/noise.h	
Noise models	359
asses/random_devices.h	
Random devices	360
asses/reversible.h	
Support for classical reversible circuits	361
asses/states.h	
Quantum states	361
asses/timer.h	
Timing	362
xperimental/experimental.h	
Experimental/test functions/classes	367
ternal/util.h	
Internal utility functions	376
ternal/classes/iomanip.h	
Input/output manipulators	374
ternal/classes/singleton.h	
Singleton pattern via CRTP	375
ATLAB/matlab.h	
Input/output interfacing with MATLAB	378

Chapter 6

Namespace Documentation

6.1 qpp Namespace Reference

Quantum++ main namespace.

Namespaces

· exception

Quantum++ exception hierarchy namespace.

· experimental

Experimental/test functions/classes, do not use or modify.

internal

Internal utility functions, do not use them directly or modify them.

literals

Classes

• class Bit_circuit

Classical reversible circuit simulator.

class Codes

const Singleton class that defines quantum error correcting codes

· class Dynamic_bitset

 $\textit{Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset < N >) \\$

· class Gates

const Singleton class that implements most commonly used gates

class IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

class Init

const Singleton class that performs additional initializations/cleanups

class IQCircuit

Quantum circuit simulator abstract class.

· struct is complex

Checks whether the type is a complex type.

- struct is_complex< std::complex< T > >

Checks whether the type is a complex number type, specialization for complex types.

· struct is_iterable

Checks whether T is compatible with an STL-like iterable container.

 $\bullet \ \ struct\ is_iterable < T,\ to_void < \ decltype(std::declval < T>().begin()),\ decltype(std::declval < T>().end()),\ decltype(*(std::declval < T>().end())),\ decltype(*(std::declval < T>().end()$

Checks whether T is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

• struct is_matrix_expression

Checks whether the type is an Eigen matrix expression.

· struct make void

Helper for qpp::to_void<> alias template.

class NoiseBase

Base class for all noise models, derive your particular noise model.

class NoiseType

Contains template tags used to specify the noise type.

class QCircuit

Quantum circuit simulator class.

· class QCircuitDescription

Quantum circuit description class.

· class QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

class QubitBitFlipNoise

Qubit bit flip noise.

• class QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

· class QubitDepolarizingNoise

Qubit depolarizing noise.

· class QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

class QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

· class QuditDepolarizingNoise

Qudit depolarizing noise.

· class RandomDevices

Singleton class that manages the source of randomness in the library.

· class States

const Singleton class that implements most commonly used states

· class Timer

Chronometer.

Typedefs

```
• template<typename... Ts>
```

```
using to_void = typename make_void < Ts... >::type
```

Alias template that implements the proposal for void_t.

• using idx = std::size t

Non-negative integer index, make sure you use an unsigned type.

• using bigint = long long int

Big integer.

using cplx = std::complex< double >

Complex number in double precision.

• using ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector. using bra = Eigen::RowVectorXcd Complex (double precision) dynamic Eigen row vector. • using cmat = Eigen::MatrixXcd Complex (double precision) dynamic Eigen matrix. using dmat = Eigen::MatrixXd Real (double precision) dynamic Eigen matrix. template<typename Scalar > using dyn mat = Eigen::Matrix < Scalar, Eigen::Dynamic, Eigen::Dynamic > Dynamic Eigen matrix over the field specified by Scalar. • template<typename Scalar > using dyn_col_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 > Dynamic Eigen column vector over the field specified by Scalar. template<typename Scalar > using dyn_row_vect = Eigen::Matrix < Scalar, 1, Eigen::Dynamic > Dynamic Eigen row vector over the field specified by Scalar. **Functions** • constexpr cplx operator"" _i (long double x) noexcept User-defined literal for complex $i = \sqrt{-1}$ (real overload) cplx omega (idx D) D-th root of unity. • template<typename Derived > dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt coefficients of the bi-partite pure state A. template<typename Derived > dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2) Schmidt coefficients of the bi-partite pure state A. template<typename Derived > cmat schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt basis on Alice side. • template<typename Derived > cmat schmidtA (const Eigen::MatrixBase< Derived > &A, idx d=2) Schmidt basis on Alice side. template<typename Derived > cmat schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt basis on Bob side. template<typename Derived > cmat schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2) Schmidt basis on Bob side. template<typename Derived > std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt probabilities of the bi-partite pure state A.

std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)

double entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)

template<typename Derived >

template<typename Derived >

Schmidt probabilities of the bi-partite pure state A.

Entanglement of the bi-partite pure state A.

```
• template<typename Derived >
  double entanglement (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Entanglement of the bi-partite pure state A.
template<typename Derived >
  double gconcurrence (const Eigen::MatrixBase< Derived > &A)
     G-concurrence of the bi-partite pure state A.
template<typename Derived >
  double negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Negativity of the bi-partite mixed state A.

    template < typename Derived >

  double negativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Negativity of the bi-partite mixed state A.

    template < typename Derived >

  double lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Logarithmic negativity of the bi-partite mixed state A.
• template<typename Derived >
  double lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Logarithmic negativity of the bi-partite mixed state A.
• template<typename Derived >
  double concurrence (const Eigen::MatrixBase< Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.
• template<typename Derived >
  double entropy (const Eigen::MatrixBase< Derived > &A)
      von-Neumann entropy of the density matrix A

    double entropy (const std::vector< double > &prob)

     Shannon entropy of the probability distribution prob.
template<typename Derived >
  double renyi (const Eigen::MatrixBase< Derived > &A, double alpha)
      Renyi- \alpha entropy of the density matrix A, for \alpha \geq 0.

    double renyi (const std::vector< double > &prob, double alpha)

     Renyi- \alpha entropy of the probability distribution prob, for \alpha > 0.
template<typename Derived >
  double tsallis (const Eigen::MatrixBase< Derived > &A, double q)
      Tsallis- q entropy of the density matrix A, for q > 0.

    double tsallis (const std::vector< double > &prob, double q)

      Tsallis- q entropy of the probability distribution prob, for q > 0.
• template<typename Derived >
  double qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx > &subsysB, const std::vector< idx > &dims)
     Quantum mutual information between 2 subsystems of a composite system.

    template<typename Derived >

  double gmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx > &subsysB, idx d=2)
      Quantum mutual information between 2 subsystems of a composite system.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > transpose (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > adjoint (const Eigen::MatrixBase< Derived > &A)
     Adjoint.
```

```
    template<typename Derived >

  dyn_mat< typename Derived::Scalar > inverse (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  Derived::Scalar trace (const Eigen::MatrixBase< Derived > &A)
      Trace
• template<typename Derived >
  Derived::Scalar det (const Eigen::MatrixBase< Derived > &A)
     Determinant.

    template<typename Derived >

  Derived::Scalar logdet (const Eigen::MatrixBase< Derived > &A)
     Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar sum (const Eigen::MatrixBase< Derived > &A)
      Element-wise sum of A.
• template<typename Derived >
  Derived::Scalar prod (const Eigen::MatrixBase< Derived > &A)
     Element-wise product of A.

    template<typename Derived >

  double norm (const Eigen::MatrixBase< Derived > &A)
     Frobenius norm.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > normalize (const Eigen::MatrixBase< Derived > &A)
     Normalizes state vector (column or row vector) or density matrix.

    template<typename Derived >

  std::pair < dyn_col_vect < cplx >, cmat > eig (const Eigen::MatrixBase < Derived > &A)
     Full eigen decomposition.

    template<typename Derived >

  dyn_col_vect< cplx > evals (const Eigen::MatrixBase< Derived > &A)
     Eigenvalues.

    template<typename Derived >

  cmat evects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors.

    template<typename Derived >

  std::pair< dyn_col_vect< double >, cmat > heig (const Eigen::MatrixBase< Derived > &A)
     Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > hevals (const Eigen::MatrixBase< Derived > &A)
     Hermitian eigenvalues.
• template<typename Derived >
  cmat hevects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors of Hermitian matrix.
• template<typename Derived >
  std::tuple< cmat, dyn_col_vect< double >, cmat > svd (const Eigen::MatrixBase< Derived > &A)
     Full singular value decomposition.

    template<typename Derived >

  dyn_col_vect< double > svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.
• template<typename Derived >
  cmat svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.

    template<typename Derived >

  cmat svdV (const Eigen::MatrixBase< Derived > &A)
```

Direct sum.

```
Right singular vectors.
• template<typename Derived >
  cmat funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)

    template<typename Derived >

  cmat sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.
template<typename Derived >
  cmat absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.

    template<typename Derived >

  cmat expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.

    template<typename Derived >

  cmat logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.
• template<typename Derived >
  cmat sinm (const Eigen::MatrixBase< Derived > &A)
     Matrix sin.

    template<typename Derived >

  cmat cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.
template<typename Derived >
  cmat spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.
• template<typename Derived >
  \label{eq:const_equation} \mbox{dyn\_mat} < \mbox{typename Derived::Scalar} > \mbox{powm (const Eigen::MatrixBase} < \mbox{Derived} > \&\mbox{A, idx n)}
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.
• template<typename Derived >
  double schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const type-
  name Derived::Scalar &))
     Functor.
template<typename T >
  dyn_mat< typename T::Scalar > kron (const T &head)
     Kronecker product.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > kron (const T &head, const Args &... tail)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > kron (const std::vector< Derived > &As)
     Kronecker product.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > kron (const std::initializer_list< Derived > &As)
     Kronecker product.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Kronecker power.

    template<typename T >

  dyn_mat< typename T::Scalar > dirsum (const T &head)
```

```
• template<typename T, typename... Args>
  dyn_mat< typename T::Scalar > dirsum (const T &head, const Args &... tail)
     Direct sum.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > dirsum (const std::vector< Derived > &As)

    template<typename Derived >

  dyn mat< typename Derived::Scalar > dirsum (const std::initializer list< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > reshape (const Eigen::MatrixBase< Derived > &A, idx rows, idx
  cols)
     Reshape.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > comm (const Eigen::MatrixBase< Derived1 > &A, const Eigen::⊷
  MatrixBase< Derived2 > &B)
     Commutator.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > prj (const Eigen::MatrixBase< Derived > &A)
     Projector.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > grams (const std::vector< Derived > &As)
     Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > grams (const std::initializer_list< Derived > &As)
      Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > grams (const Eigen::MatrixBase< Derived > &A)
     Gram-Schmidt orthogonalization.

    std::vector< idx > n2multiidx (idx n, const std::vector< idx > &dims)

     Non-negative integer index to multi-index.

    idx multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

     Multi-index to non-negative integer index.

    ket mket (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Multi-partite qudit ket.

    ket mket (const std::vector< idx > &mask, idx d=2)

     Multi-partite qudit ket.

    cmat mprj (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Projector onto multi-partite qudit ket.

    cmat mprj (const std::vector < idx > &mask, idx d=2)

     Projector onto multi-partite qudit ket.
• template<typename InputIterator >
  std::vector< double > abssq (InputIterator first, InputIterator last)
```

Computes the absolute values squared of an STL-like range of complex numbers.

• template<typename Container >

std::vector< double > abssq (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Computes the absolute values squared of an STL-like container.

template<typename Derived >

```
std::vector< double > abssq (const Eigen::MatrixBase< Derived > &A)
```

Computes the absolute values squared of an Eigen expression.

template<typename InputIterator >

std::iterator_traits< InputIterator >::value_type sum (InputIterator first, InputIterator last)

Element-wise sum of an STL-like range.

• template<typename Container >

Container::value_type sum (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

std::iterator traits < InputIterator >::value type prod (InputIterator first, InputIterator last)

Element-wise product of an STL-like range.

• template<typename Container >

Container::value_type prod (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Element-wise product of the elements of an STL-like container.

template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > rho2pure (const Eigen::MatrixBase< Derived > &A)
```

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

std::vector< idx > complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

• template<typename Derived >

```
std::vector< double > rho2bloch (const Eigen::MatrixBase< Derived > &A)
```

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

• template<typename Derived >

internal::IOManipEigen disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)

Eigen expression ostream manipulator.

internal::IOManipEigen disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

• template<typename InputIterator >

internal::IOManipRange < InputIterator > disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")

Range ostream manipulator.

 $\bullet \ \ \text{template}{<} \text{typename Container} >$

internal::IOManipRange< typename Container::const_iterator > disp (const Container &c, const std::string &separator, const std::string &start="[", const std::string &end="]", typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

template<typename PointerType >

internal::IOManipPointer< PointerType > disp (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")

C-style pointer ostream manipulator.

template<typename Derived >

```
void save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)
```

Saves Eigen expression to a binary file (internal format) in double precision.

template<typename Derived >

dyn_mat< typename Derived::Scalar > load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.

• template<typename Derived >

 $\label{lem:dyn_col_vect} $$ \displaystyle \operatorname{dyn_col_vect} < \operatorname{typename \ Derived}::Scalar > ip (const \ Eigen::MatrixBase < \operatorname{Derived} > & phi, const \ Eigen:: \longleftrightarrow \\ \operatorname{MatrixBase} < \operatorname{Derived} > & psi, const \ std::vector < idx > & subsys, const \ std::vector < idx > & dims) \\ $$ \displaystyle \operatorname{dyn_col_vect} < \operatorname{dyn_col_v$

Generalized inner product.

• template<typename Derived >

dyn_col_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template<typename Derived >

 $std::tuple < std::vector < idx >, \ double, \ cmat > measure_seq \ (const \ Eigen::MatrixBase < Derived > \&A, \\ std::vector < idx > target, \ idx \ d=2)$

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

ullet template<typename Derived >

 $std::enable_if < std::is_same < typename Derived::Scalar, cplx >::value, dyn_mat < cplx > ::type \\ loadMATLAB (const std::string &mat_file, const std::string &var_name)$

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::

Scalar > >::type loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

std::vector< int > x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

bigint gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > invperm (const std::vector< idx > &perm)

Inverse permutation.

• std::vector< idx > compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

std::vector< bigint > factors (bigint a)

Prime factor decomposition.

• bigint modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

bigint modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple < bigint, bigint, bigint > egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint modinv (bigint a, bigint p)

Modular inverse of a mod p.

bool isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

bigint randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

std::vector< std::pair< int, int > > convergents (const std::vector< int > &cf)

Convergents

std::vector< std::pair< int, int > > convergents (double x, idx N)

Convergents.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, const
std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

- template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, idx
d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)
```

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

template<typename Derived >

cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, const std::vector< idx > &dims)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

• template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, idx d=2)
```

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat kraus2super (const std::vector < cmat > &Ks)

Superoperator matrix.

cmat kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector< cmat > choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

template<typename Derived >

```
\label{lem:dyn_mat}  \mbox{dyn\_mat} < \mbox{typename Derived::Scalar} > \mbox{ptrace1} \mbox{ (const Eigen::MatrixBase} < \mbox{Derived} > \&\mbox{A, const std} \\ \mbox{::vector} < \mbox{idx} > \&\mbox{dims})
```

Partial trace.

 $\bullet \ \ {\sf template}{<} {\sf typename \ Derived} >$

```
dyn_mat< typename Derived::Scalar > ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.
```

template<typename Derived >

```
\frac{dyn\_mat<}{typename} \ Derived::Scalar > ptrace2 \ (const \ Eigen::MatrixBase< \ Derived > \&A, \ const \ std \\ \because vector < idx > \&dims)
```

Partial trace.

• template<typename Derived >

```
dyn_mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)
```

Partial trace.

ullet template<typename Derived >

 $\frac{dyn_mat}{dx}$ typename Derived::Scalar > $\frac{dyn_mat}{dx}$ (const Eigen::MatrixBase < Derived > &A, const std::vector < $\frac{dx}{dx}$ > &target, const std::vector < $\frac{dx}{dx}$ > &dims)

Partial trace.

ullet template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector
idx > &target, idx d=2)

Partial trace.

template<typename Derived >

Partial transpose.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptranspose (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial transpose.

• template<typename Derived >

Subsystem permutation.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > syspermute (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &perm, idx d=2)

Subsystem permutation.

template<typename Derived >

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_mat< typename Derived::Scalar > applyTFQ (const Eigen::MatrixBase< Derived > &A, const std↔ ::vector< idx > &target, idx d=2, bool swap=true)

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool
swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool
swap=true)

Qudit quantum Fourier transform.

• double rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

• bigint rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx randidx (idx a=std::numeric_limits < idx >::min(), idx b=std::numeric_limits < idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

Derived rand (idx rows, idx cols, double a=0, double b=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

• template<>

dmat rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (gpp::dmat)

• template<>

cmat rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived randn (idx rows, idx cols, double mean=0, double sigma=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

dmat randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

template<>

cmat randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

• double randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

• cmat randU (idx D=2)

Generates a random unitary matrix.

· cmat randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat randH (idx D=2)

Generates a random Hermitian matrix.

• ket randket (idx D=2)

Generates a random normalized ket (pure state vector)

cmat randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.

std::vector< double > uniform (idx N)

Uniform probability distribution vector.

std::vector< double > marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > marginalY (const dmat &probXY)

Marginal distribution.

 $\bullet \ \ \text{template}{<} \text{typename Container} >$

double avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable<
Container >::value >::type *=nullptr)

Average.

• template<typename Container >

double cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is iterable< Container >::value >::type *=nullptr)

Covariance.

• template<typename Container >

double var (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable<
Container >::value >::type *=nullptr)

Variance.

template<typename Container >
 double sigma (const std::vector< double > &prob, const Container &X, typename std::enable_if<
 is_iterable< Container >::value >::type *=nullptr)

Standard deviation.

• template<typename Container >

double cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Correlation.

Variables

• constexpr double chop = 1e-10

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

constexpr double eps = std::numeric_limits<double>::epsilon()

Used to decide whether a number or expression in double precision is zero or not for the purpose of a specific computation.

• constexpr idx maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

constexpr double pi = 3.141592653589793238462643383279502884

 π

constexpr double ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

constexpr double infty = std::numeric_limits<double>::max()

Used to denote infinity in double precision.

const idx idx infty = static cast<idx>(-1)

Used to denote the largest unsigned index.

6.1.1 Detailed Description

Quantum++ main namespace.

6.1.2 Typedef Documentation

6.1.2.1 bigint

```
using qpp::bigint = typedef long long int
```

Big integer.

6.1.2.2 bra

```
using qpp::bra = typedef Eigen::RowVectorXcd
```

Complex (double precision) dynamic Eigen row vector.

```
6.1.2.3 cmat
```

```
using qpp::cmat = typedef Eigen::MatrixXcd
```

Complex (double precision) dynamic Eigen matrix.

6.1.2.4 cplx

```
using qpp::cplx = typedef std::complex<double>
```

Complex number in double precision.

6.1.2.5 dmat

```
using qpp::dmat = typedef Eigen::MatrixXd
```

Real (double precision) dynamic Eigen matrix.

6.1.2.6 dyn_col_vect

```
template<typename Scalar >
using qpp::dyn_col_vect = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, 1>
```

Dynamic Eigen column vector over the field specified by Scalar.

Example:

```
// type of colvect is Eigen::Matrix<float, Eigen::Dynamic, 1>
dyn_col_vect<float> colvect(2);
```

6.1.2.7 dyn_mat

```
template<typename Scalar >
using qpp::dyn_mat = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, Eigen::Dynamic>
```

Dynamic Eigen matrix over the field specified by Scalar.

Example:

```
// type of mat is Eigen::Matrix<float, Eigen::Dynamic, Eigen::Dynamic>
dyn_mat<float> mat(2, 3);
```

```
6.1.2.8 dyn_row_vect
```

```
template<typename Scalar >
using qpp::dyn_row_vect = typedef Eigen::Matrix<Scalar, 1, Eigen::Dynamic>
```

Dynamic Eigen row vector over the field specified by Scalar.

Example:

```
// type of rowvect is Eigen::Matrix<float, 1, Eigen::Dynamic>
dyn_row_vect<float> rowvect(3);
```

6.1.2.9 idx

```
using qpp::idx = typedef std::size_t
```

Non-negative integer index, make sure you use an unsigned type.

6.1.2.10 ket

```
using qpp::ket = typedef Eigen::VectorXcd
```

Complex (double precision) dynamic Eigen column vector.

6.1.2.11 to_void

```
template<typename... Ts>
using qpp::to_void = typedef typename make_void<Ts...>::type
```

Alias template that implements the proposal for void_t.

See also

```
http://www.open-std.org/jtc1/sc22/wg21/docs/papers/2014/n3911
```

6.1.3 Function Documentation

6.1.3.1 absm()

Matrix absolute value.

Parameters

```
A Eigen expression
```

Returns

Matrix absolute value of A

Computes the absolute values squared of an STL-like range of complex numbers.

Parameters

	Iterator to the first element of the range
last	Iterator to the last element of the range

InputIterator last)

Returns

Real vector consisting of the range absolute values squared

```
6.1.3.3 abssq() [2/3]
```

Computes the absolute values squared of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Real vector consisting of the container's absolute values squared

Computes the absolute values squared of an Eigen expression.

Parameters

```
A Eigen expression
```

Returns

Real vector consisting of the absolute values squared

6.1.3.5 adjoint()

Adjoint.

Parameters

```
A Eigen expression
```

Returns

Adjoint (Hermitian conjugate) of A, as a dynamic matrix over the same scalar field as A

6.1.3.6 anticomm()

Anti-commutator.

See also

qpp::comm()

Anti-commutator $\{A,B\} = AB + BA$. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
В	Eigen expression

Returns

Anti-commutator AB + BA, as a dynamic matrix over the same scalar field as A

6.1.3.7 apply() [1/5]

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

Returns

Gate A applied to the part target of state

6.1.3.8 apply() [2/5]

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

Returns

Gate A applied to the part target of state

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes where the Kraus operators Ks are applied
dims	Dimensions of the multi-partite system

Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes where the Kraus operators Ks are applied
d	Subsystem dimensions

Returns

Output density matrix after the action of the channel

6.1.3.12 applyCTRL() [1/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate *A* must match the dimension of *target*. Also, all control subsystems in *ctrl* must have the same dimension.

Parameters

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

Returns

CTRL-A gate applied to the part target of state

6.1.3.13 applyCTRL() [2/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

Returns

CTRL-A gate applied to the part target of state

6.1.3.14 applyQFT()

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

Parameters

Α	Eigen expression
target	Subsystem indexes where the QFT is applied
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Qudit Quantum Fourier transform applied to the part target of A

6.1.3.15 applyTFQ()

Applies the inverse (adjoint) qudit quantum Fourier transform to the part *target* of the multi-partite state vector or density matrix *A*.

Parameters

Α	Eigen expression
target	Subsystem indexes where the TFQ is applied
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Inverse (adjoint) qudit Quantum Fourier transform applied to the part target of A

6.1.3.16 avg()

Average.

Parameters

prob	Real probability vector representing the probability distribution of X
Χ	Real random variable values represented by an STL-like container

Returns

Average of X

6.1.3.17 bloch2rho()

Computes the density matrix corresponding to the 3-dimensional real Bloch vector *r*.

See also

qpp::rho2bloch()

Parameters

r 3-dimensional real vector

Returns

Qubit density matrix

6.1.3.18 choi2kraus()

Orthogonal Kraus operators from Choi matrix.

See also

qpp::kraus2choi()

Extracts a set of orthogonal (under Hilbert-Schmidt operator norm) Kraus operators from the Choi matrix A

Note

The Kraus operators satisfy $Tr(K_i^{\dagger}K_j)=\delta_{ij}$ for all $i\neq j$

Parameters



Returns

Set of orthogonal Kraus operators


6.1.3.19 choi2super()

Converts Choi matrix to superoperator matrix.

See also

qpp::super2choi()

Parameters



Returns

Superoperator matrix

6.1.3.20 comm()

Commutator.

See also

qpp::anticomm()

Commutator [A, B] = AB - BA. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
В	Eigen expression

Returns

Commutator AB - BA, as a dynamic matrix over the same scalar field as A

6.1.3.21 complement()

Constructs the complement of a subsystem vector.

Parameters

subsys	Subsystem vector
n	Total number of systems

Returns

Complement of *subsys* with respect to the set $\{0, 1, \dots, n-1\}$

6.1.3.22 compperm()

Compose permutations.

Parameters

perm	Permutation
sigma	Permutation

Returns

Composition of the permutations *perm* o *sigma* = perm(sigma)

6.1.3.23 concurrence()

Wootters concurrence of the bi-partite qubit mixed state A.

Parameters

```
A Eigen expression
```

Returns

Wootters concurrence

6.1.3.24 conjugate()

Complex conjugate.

Parameters

```
A Eigen expression
```

Returns

Complex conjugate of A, as a dynamic matrix over the same scalar field as A

6.1.3.25 contfrac2x()

Real representation of a simple continued fraction.

See also

```
qpp::x2contfrac()
```

Note

If N is greater than the size of cf (by default it is), then all terms in cf are considered.

Parameters

	Integer vector containing the simple continued fraction expansion
Ν	Number of terms considered in the continued fraction expansion.

Returns

Real representation of the simple continued fraction

6.1.3.26 convergents() [1/2]

```
std::vector<std::pair<int, int> > qpp::convergents ( const std::vector< int > & cf ) [inline]
```

Convergents.

See also

```
qpp::contfrac2x() and qpp::x2contfrac()
```

Parameters

```
cf Continued fraction
```

Returns

Vector of convergents pairs (a_k, b_k) that approximate the number represented by the continued fraction

6.1.3.27 convergents() [2/2]

```
std::vector<std::pair<int, int> > qpp::convergents ( double x, idx N) [inline]
```

Convergents.

See also

```
qpp::contfrac2x() and qpp::x2contfrac()
```

Note

In the continued fraction expansion of x has less terms than N, then the series of convergents is truncated to the number of terms in the continued fraction expansion of x.

Parameters

Х	Real number
Ν	Number of convergents.

Returns

Vector of convergents pairs (a_k,b_k) that approximate the number \emph{x}

6.1.3.28 cor()

Correlation.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels the rows, Y labels the columns)
X	Real random variable values represented by an STL-like container
Y	Real random variable values represented by an STL-like container

Returns

Correlation of X and Y

6.1.3.29 cosm()

Matrix cos.

Parameters

```
A Eigen expression
```

Returns

Matrix cosine of A

6.1.3.30 cov()

Covariance.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels the rows, Y labels the columns)
Χ	Real random variable values represented by an STL-like container
Y	Real random variable values represented by an STL-like container

Returns

Covariance of X and Y

6.1.3.31 cwise()

Functor.

Parameters

Α	Eigen expression
f	Pointer-to-function from scalars of A to OutputScalar

Returns

Component-wise f(A), as a dynamic matrix over the *OutputScalar* scalar field

6.1.3.32 det()

Determinant.

Parameters

A Eigen expression

Returns

Determinant of A, as a scalar over the same scalar field as A. Returns $\pm \infty$ when the determinant overflows/underflows.

```
6.1.3.33 dirsum() [1/4]
```

Direct sum.

See also

qpp::dirsumpow()

Used to stop the recursion for the variadic template version of qpp::dirsum()

Parameters

head	Eigen expression
ncau	Ligon capicosion

Its argument head

Direct sum.

See also

qpp::dirsumpow()

Parameters

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

Returns

Direct sum of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

```
6.1.3.35 dirsum() [3/4]
```

Direct sum.

See also

qpp::dirsumpow()

Parameters

As std::vector of Eigen expressions

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Direct sum.

See also

qpp::dirsumpow()

Parameters

As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}

Returns

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.3.37 dirsumpow()

Direct sum power.

See also

qpp::dirsum()

Parameters

Α	Eigen expression
n	Non-negative integer

Direct sum of A with itself n times $A^{\oplus n}$, as a dynamic matrix over the same scalar field as A

Eigen expression ostream manipulator.

Parameters

Α	Eigen expression
chop	Set to zero the elements smaller in absolute value than <i>chop</i>

Returns

Instance of qpp::internal::IOManipEigen

Complex number ostream manipulator.

Parameters

Z	Complex number (or any other type implicitly cast-able to std::complex <double>)</double>
chop	Set to zero the elements smaller in absolute value than chop

Returns

Instance of qpp::internal::IOManipEigen

```
6.1.3.40 disp() [3/5]

template<typename InputIterator >
internal::IOManipRange<InputIterator> qpp::disp (
```

```
InputIterator first,
InputIterator last,
const std::string & separator,
const std::string & start = "[",
const std::string & end = "]")
```

Range ostream manipulator.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipRange

```
6.1.3.41 disp() [4/5]
```

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

Parameters

С	Container
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipRange

6.1.3.42 disp() [5/5]

```
template<typename PointerType >
internal::IOManipPointer<PointerType> qpp::disp (
```

```
const PointerType * p,
idx N,
const std::string & separator,
const std::string & start = "[",
const std::string & end = "]")
```

C-style pointer ostream manipulator.

Parameters

р	Pointer to the first element
N	Number of elements to be displayed
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipPointer

6.1.3.43 egcd()

Extended greatest common divisor of two integers.

See also

qpp::gcd()

Parameters

а	Integer
b	Integer

Returns

Tuple of: 1. Integer m, 2. Integer n, and 3. Non-negative integer gcd(a,b) such that ma + nb = gcd(a,b)

6.1.3.44 eig()

Full eigen decomposition.

See also

qpp::heig()

Parameters

```
A Eigen expression
```

Returns

Pair of: 1. Eigenvalues of *A*, as a complex dynamic column vector, and 2. Eigenvectors of *A*, as columns of a complex dynamic matrix

6.1.3.45 entanglement() [1/2]

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

```
qpp::entropy()
```

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Entanglement, with the logarithm in base 2

6.1.3.46 entanglement() [2/2]

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

qpp::entropy()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Entanglement, with the logarithm in base 2

6.1.3.47 entropy() [1/2]

von-Neumann entropy of the density matrix A

Parameters

```
A Eigen expression
```

Returns

von-Neumann entropy, with the logarithm in base 2

6.1.3.48 entropy() [2/2]

Shannon entropy of the probability distribution prob.

Parameters

prob Real probability vector

Returns

Shannon entropy, with the logarithm in base 2

```
6.1.3.49 evals()
```

Eigenvalues.

See also

qpp::hevals()

Parameters

```
A Eigen expression
```

Returns

Eigenvalues of A, as a complex dynamic column vector

6.1.3.50 evects()

Eigenvectors.

See also

qpp::hevects()

Parameters

```
A Eigen expression
```

Returns

Eigenvectors of A, as columns of a complex dynamic matrix

6.1.3.51 expm()

Matrix exponential.

Parameters

A Eigen expression

Returns

Matrix exponential of A

6.1.3.52 factors()

Prime factor decomposition.

Note

Runs in $\mathcal{O}(\sqrt{n})$ time complexity

Parameters

a Integer different from 0, 1 or -1

Returns

Integer vector containing the factors

6.1.3.53 funm()

Functional calculus f(A)

Parameters

Α	Eigen expression
f	Pointer-to-function from complex to complex

```
Returns
```

```
f(A)
```

Greatest common divisor of two integers.

See also

```
qpp::lcm()
```

Parameters

а	Integer
b	Integer

Returns

Greatest common divisor of a and b

Greatest common divisor of a list of integers.

See also

```
qpp::lcm()
```

Parameters

```
as List of integers
```

Returns

Greatest common divisor of all numbers in as

6.1.3.56 gconcurrence()

G-concurrence of the bi-partite pure state A.

Note


Both local dimensions must be equal

Uses qpp::logdet() to avoid overflows

See also

qpp::logdet()

Parameters



Returns

G-concurrence

```
6.1.3.57 grams() [1/3]
```

Gram-Schmidt orthogonalization.

Parameters

```
As std::vector of Eigen expressions as column vectors
```

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

```
6.1.3.58 grams() [2/3]
```

Gram-Schmidt orthogonalization.

Parameters

```
As std::initializer_list of Eigen expressions as column vectors
```

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

Gram-Schmidt orthogonalization.

Parameters

A Eigen expression, the input vectors are the columns of A

Returns

Gram-Schmidt vectors of the columns of A, as columns of a dynamic matrix over the same scalar field as A

6.1.3.60 heig()

Full eigen decomposition of Hermitian expression.

See also

qpp::eig()

Parameters

A Eigen expression

Pair of: 1. Eigenvalues of A, as a real dynamic column vector, and 2. Eigenvectors of A, as columns of a complex dynamic matrix

6.1.3.61 hevals()

Hermitian eigenvalues.

See also

qpp::evals()

Parameters

A Eigen expression

Returns

Eigenvalues of Hermitian A, as a real dynamic column vector

6.1.3.62 hevects()

Eigenvectors of Hermitian matrix.

See also

qpp::evects()

Parameters

A Eigen expression

Returns

Eigenvectors of Hermitian matrix A, as columns of a complex matrix

6.1.3.63 inverse()

Inverse.

Parameters

```
A Eigen expression
```

Returns

Inverse of A, as a dynamic matrix over the same scalar field as A

6.1.3.64 invperm()

```
\label{eq:std:vector} $$ std::vector < idx > & perm ) $$ [inline] $$
```

Inverse permutation.

Parameters

perm Permut	ation
-------------	-------

Returns

Inverse of the permutation perm

6.1.3.65 ip() [1/2]

Generalized inner product.

Parameters

phi	hi Column vector Eigen expression	
psi	Column vector Eigen expression	
subsys	Subsystem indexes over which phi is defined	
dims	Dimensions of the multi-partite system	

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

Generalized inner product.

Parameters

phi	Column vector Eigen expression
psi	Column vector Eigen expression
subsys	Subsystem indexes over which phi is defined
d	Subsystem dimensions

Returns

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

6.1.3.67 isprime()

Primality test based on the Miller-Rabin's algorithm.

Parameters

p	Integer different from 0, 1 or -1
k	Number of iterations. The probability of a false positive is 2^{-k} .

Returns

True if the number is (most-likely) prime, false otherwise

6.1.3.68 kraus2choi()

Choi matrix.

See also

qpp::choi2kraus()

Constructs the Choi matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|, |0\rangle\langle 1|$ etc.

Note

The superoperator matrix S and the Choi matrix C are related by $S_{ab,mn}=C_{ma,nb}$

Parameters

Ks Set of Kraus operators

Returns

Choi matrix

6.1.3.69 kraus2super()

Superoperator matrix.

Constructs the superoperator matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|$, $|0\rangle\langle 1|$ etc.

Parameters

Ks Set of Kraus operators

Returns

Superoperator matrix

Kronecker product.

See also

qpp::kronpow()

Used to stop the recursion for the variadic template version of app::kron()

Parameters

head	Eigen expression
------	------------------

Returns

Its argument head

```
6.1.3.71 kron() [2/4]
```

Kronecker product.

See also

qpp::kronpow()

Parameters

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

Returns

Kronecker product of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

See also

qpp::kronpow()

Parameters

As std::vector of Eigen expressions

Returns

Kronecker product of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Kronecker product.

See also

qpp::kronpow()

Parameters

As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}

Returns

Kronecker product of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.3.74 kronpow()

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::kronpow (
```

```
const Eigen::MatrixBase< Derived > & A, idx n)
```

Kronecker power.

See also

qpp::kron()

Parameters

Α	Eigen expression
n	Non-negative integer

Returns

Kronecker product of A with itself n times $A^{\otimes n}$, as a dynamic matrix over the same scalar field as A

Least common multiple of two integers.

See also

qpp::gcd()

Parameters

а	Integer
b	Integer

Returns

Least common multiple of a and b

Least common multiple of a list of integers.

See also

```
qpp::gcd()
```

Parameters

```
as List of integers
```

Returns

Least common multiple of all numbers in as

6.1.3.77 load()

Loads Eigen matrix from a binary file (internal format) in double precision.

See also

```
qpp::save()
```

The template parameter cannot be automatically deduced and must be explicitly provided, depending on the scalar field of the matrix that is being loaded.

Example:

```
// loads a previously saved Eigen dynamic complex matrix from "input.bin" cmat mat = load<cmat>("input.bin");
```

Parameters

```
fname Output file name
```

6.1.3.78 loadMATLAB() [1/2]

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

```
qpp::saveMATLAB()
```

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen ket
// from the MATLAB file "input.mat"
ket psi = loadMATLABket>("input.mat");
```

Template Parameters

Derived	Complex Eigen type
---------	--------------------

Parameters

mat_file	MATALB .mat file	
var_name	Variable name in the .mat file representing the matrix to be loaded]

Returns

Eigen dynamic matrix

6.1.3.79 loadMATLAB() [2/2]

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

```
qpp::saveMATLAB()
```

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen dynamic double matrix
// from the MATLAB file "input.mat"
dmat mat = loadMATLAB<dmat>("input.mat");
```

Template Parameters

е
е

Parameters

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be loaded

Returns

Eigen dynamic matrix

6.1.3.80 logdet()

Logarithm of the determinant.

Useful when the determinant overflows/underflows

Parameters

```
A Eigen expression
```

Returns

Logarithm of the determinant of A, as a scalar over the same scalar field as A

6.1.3.81 logm()

Matrix logarithm.

Parameters

A Eigen expression

Matrix logarithm of A

Logarithmic negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Logarithmic negativity, with the logarithm in base 2

6.1.3.83 lognegativity() [2/2]

```
template<typename Derived >
double qpp::lognegativity (
          const Eigen::MatrixBase< Derived > & A,
          idx d = 2 )
```

Logarithmic negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Logarithmic negativity, with the logarithm in base 2

6.1.3.84 marginalX()

Marginal distribution.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels	1
	the rows, Y labels the columns)	

Returns

Real vector consisting of the marginal distribution of X

6.1.3.85 marginalY()

Marginal distribution.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels	
	the rows, Y labels the columns)	

Returns

Real vector consisting of the marginal distribution of Y

6.1.3.86 measure() [1/9]

Measures the state vector or density operator A using the set of Kraus operators Ks.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.87 measure() [2/9]

Measures the state vector or density matrix A using the set of Kraus operators Ks.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.88 measure() [3/9]

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

Parameters

Α	Eigen expression	
U	Unitary matrix whose columns represent the measurement basis vectors	

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.89 measure() [4/9]

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.90 measure() [5/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.92 measure() [7/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.93 measure() [8/9]

Measures the part *target* of the multi-partite state vector or density matrix *A* in the orthonormal basis or rank-1 projectors specified by the columns of the matrix *V*.

See also

```
qpp::measure_seq()
```

Note

The dimension of V must match the dimension of target. The measurement is destructive, i.e. the measured subsystems are traced away.

Α	Eigen expression
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part *target* of the multi-partite state vector or density matrix *A* in the orthonormal basis or rank-1 projectors specified by the columns of the matrix *V*.

See also

```
qpp::measure_seq()
```

Note

The dimension of *V* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression	
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors	
target	Subsystem indexes that are measured	
d	Subsystem dimensions	

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

See also

qpp::measure()

Parameters

Α	Eigen expression
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

See also

qpp::measure()

Parameters

Α	Eigen expression
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|\text{mask}\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

Parameters

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

Returns

Multi-partite qudit state vector, as a complex dynamic column vector

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Multi-partite qudit state vector, as a complex dynamic column vector

6.1.3.99 modinv()

Modular inverse of a mod p.

See also

```
qpp::egcd()
```

Note

a and p must be co-prime

Parameters

а	Non-negative integer
р	Non-negative integer

Returns

```
Modular inverse a^{-1} \mod p
```

6.1.3.100 modmul()

```
bigint qpp::modmul (
                bigint a,
                bigint b,
                bigint p ) [inline]
```

Modular multiplication without overflow.

Computes $ab \bmod p$ without overflow

Parameters

а	Integer
b	Integer
р	Positive integer

Returns

 $ab \bmod p$ avoiding overflow

6.1.3.101 modpow()

```
bigint qpp::modpow (
          bigint a,
```

```
bigint n,
bigint p ) [inline]
```

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

Note

Uses qpp::modmul() that avoids overflows

Computes $a^n \bmod p$

Parameters

а	Non-negative integer
n	Non-negative integer
р	Strictly positive integer

Returns

```
a^n \bmod p
```

const std::vector< idx > & dims) [inline]

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

Parameters

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

6.1.3.104 multiidx2n()

Multi-index to non-negative integer index.

See also

```
qpp::n2multiidx()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

Parameters

midx	Multi-index
dims	Dimensions of the multi-partite system

Returns

Non-negative integer index

6.1.3.105 n2multiidx()

```
\label{eq:std::vector} $$ std::vector < idx > qpp::n2multiidx ($$ idx n,$$ const std::vector < idx > & dims ) [inline]
```

Non-negative integer index to multi-index.

See also

```
qpp::multiidx2n()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

Parameters

n	Non-negative integer index
dims	Dimensions of the multi-partite system

Returns

Multi-index of the same size as dims

6.1.3.106 negativity() [1/2]

Negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Negativity

6.1.3.107 negativity() [2/2]

```
template<typename Derived >
double qpp::negativity (
```

```
const Eigen::MatrixBase< Derived > & A, idx d = 2)
```

Negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Negativity

6.1.3.108 norm()

Frobenius norm.

Parameters

```
A Eigen expression
```

Returns

Frobenius norm of A

6.1.3.109 normalize()

Normalizes state vector (column or row vector) or density matrix.

Parameters

A Eigen expression

Normalized state vector or density matrix

```
6.1.3.110 omega()

cplx qpp::omega (
          idx D ) [inline]
```

D-th root of unity.

Parameters

D Non-negative integer

6.1.3.111 operator""" _i()

Returns

D-th root of unity $\exp(2\pi i/D)$

User-defined literal for complex $i = \sqrt{-1}$ (real overload)

Example:

```
cplx z = 4.5_i; // type of z is std::complex<double>
```

6.1.3.112 powm()

Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

See also

```
qpp::spectralpowm()
```

Explicitly multiplies the matrix A with itself n times. By convention $A^0 = I$.

Α	Eigen expression
n	Non-negative integer

Returns

Matrix power A^n , as a dynamic matrix over the same scalar field as A

6.1.3.113 prj()

Projector.

Normalized projector onto state vector

Parameters

```
A Eigen expression
```

Returns

Projector onto the state vector A, or the matrix Zero if A has norm zero (i.e. smaller than qpp::eps), as a dynamic matrix over the same scalar field as A

6.1.3.114 prod() [1/3]

Element-wise product of A.

Parameters

```
A Eigen expression
```

Returns

Element-wise product of A, as a scalar over the same scalar field as A

Element-wise product of an STL-like range.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

InputIterator last)

Returns

Element-wise product of the range, as a scalar over the same scalar field as the range

Element-wise product of the elements of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Element-wise product of the elements of the container, as a scalar over the same scalar field as the container

See also

Partial trace.

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Returns

Partial trace $Tr_{subsys}(\cdot)$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

Partial trace.

See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial trace $Tr_{subsys}(\cdot)$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

```
6.1.3.119 ptrace1() [1/2]
```

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_A(\cdot)$ over the first subsytem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.120 ptrace1() [2/2]

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_A(\cdot)$ over the first subsystem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.121 ptrace2() [1/2]

Partial trace.

See also

```
qpp::ptrace1()
```

Partial trace over the second subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_B(\cdot)$ over the second subsytem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.122 ptrace2() [2/2]

Partial trace.

See also

qpp::ptrace1()

Partial trace over the second subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_B(\cdot)$ over the second subsytem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.123 ptranspose() [1/2]

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::ptranspose (
```

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & target,
const std::vector< idx > & dims )
```

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.3.124 ptranspose() [2/2]

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.3.125 QFT()

```
template<typename Derived >
dyn_col_vect<typename Derived::Scalar> qpp::QFT (
```

```
const Eigen::MatrixBase< Derived > & A, idx d = 2, bool swap = true)
```

Qudit quantum Fourier transform.

Parameters

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Qudit quantum Fourier transform applied on A

6.1.3.126 qmutualinfo() [1/2]

Quantum mutual information between 2 subsystems of a composite system.

Parameters

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
dims	Dimensions of the multi-partite system

Returns

Mutual information between the 2 subsystems

6.1.3.127 qmutualinfo() [2/2]

Quantum mutual information between 2 subsystems of a composite system.

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
d	Subsystem dimensions

Returns

Mutual information between the 2 subsystems

Generates a random real number uniformly distributed in the interval [a, b)

Parameters

a	ì	Beginning of the interval, belongs to it
b)	End of the interval, does not belong to it

Returns

Random real number (double) uniformly distributed in the interval [a, b)

Generates a random big integer uniformly distributed in the interval [a, b].

Note

To avoid ambiguity with double qpp::rand(double, double) cast at least one of the arguments to qpp::bigint

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

Random big integer uniformly distributed in the interval [a, b]

Generates a random matrix with entries uniformly distributed in the interval [a, b)

If complex, then both real and imaginary parts are uniformly distributed in [a, b)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries uniformly distributed in [-1,1)
dmat mat = rand<dmat>(3, 3, -1, 1);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd,
// with entries (both real and imaginary) uniformly distributed in [-1,1)
cmat mat = rand<cmat>(3, 3, -1, 1);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Returns

Random complex matrix

6.1.3.133 randH()

```
cmat qpp::randH (
    idx D = 2) [inline]
```

Generates a random Hermitian matrix.

Parameters

D Dimension of the Hilbert space

Random Hermitian matrix

6.1.3.134 randidx()

```
idx qpp::randidx (
        idx a = std::numeric_limits<idx>::min(),
        idx b = std::numeric_limits<idx>::max() ) [inline]
```

Generates a random index (idx) uniformly distributed in the interval [a, b].

Parameters

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

Returns

Random index (idx) uniformly distributed in the interval [a, b]

6.1.3.135 randket()

```
ket qpp::randket (
idx D = 2) [inline]
```

Generates a random normalized ket (pure state vector)

Parameters

D Dimension of the Hilbert space

Returns

Random normalized ket

6.1.3.136 randkraus()

```
std::vector<cmat> qpp::randkraus (
    idx N,
    idx D = 2 ) [inline]
```

Generates a set of random Kraus operators.

Note

The set of Kraus operators satisfy the closure condition $\sum_i K_i^\dagger K_i = I$

Parameters

N	Number of Kraus operators
D	Dimension of the Hilbert space

Returns

Set of N Kraus operators satisfying the closure condition

Generates a random matrix with entries normally distributed in N(mean, sigma)

If complex, then both real and imaginary parts are normally distributed in N(mean, sigma)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries normally distributed in N(0,2)
dmat mat = randn<dmat>(3, 3, 0, 2);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Returns

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd, 
// with entries (both real and imaginary) normally distributed in N(0,2) cmat mat = randn<cmat>(3, 3, 0, 2);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Returns

Random complex matrix

Generates a random real number (double) normally distributed in N(mean, sigma)

Parameters

mean	Mean
sigma	Standard deviation

Returns

Random real number normally distributed in N(mean, sigma)

6.1.3.141 randperm()

```
std::vector<idx> qpp::randperm (
    idx N ) [inline]
```

Generates a random uniformly distributed permutation.

Uses Knuth shuffle method (as implemented by std::shuffle), so that all permutations are equally probable

Parameters

```
N Size of the permutation
```

Returns

Random permutation of size N

6.1.3.142 randprime()

```
bigint qpp::randprime (
          bigint a,
          bigint b,
          idx N = 1000 ) [inline]
```

Generates a random big prime uniformly distributed in the interval [a, b].

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it
N	Maximum number of candidates

Random big integer uniformly distributed in the interval [a, b]

6.1.3.143 randprob()

```
\label{eq:std::vector} $$ \std::vector<double> qpp::randprob ( idx N) [inline]
```

Generates a random probability vector uniformly distributed over the probability simplex.

Parameters

N Size of the probability vector

Returns

Random probability vector

6.1.3.144 randrho()

```
cmat qpp::randrho (
    idx D = 2 ) [inline]
```

Generates a random density matrix.

Parameters

D Dimension of the Hilbert space

Returns

Random density matrix

6.1.3.145 randU()

```
cmat qpp::randU (
    idx D = 2) [inline]
```

Generates a random unitary matrix.

D Dimension of the Hilbert space

Returns

Random unitary

6.1.3.146 randV()

Generates a random isometry matrix.

Parameters

Din	Size of the input Hilbert space
Dout	Size of the output Hilbert space

Returns

Random isometry matrix

```
6.1.3.147 renyi() [1/2]
```

Renyi- α entropy of the density matrix ${\it A}$, for $\alpha \geq 0$.

Note

When $\alpha \to 1$ the Renyi entropy converges to the von-Neumann entropy, with the logarithm in base 2

Α	Eigen expression
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

Renyi- α entropy, with the logarithm in base 2

Renyi- α entropy of the probability distribution *prob*, for $\alpha \geq 0$.

Note

When $\alpha \to 1$ the Renyi entropy converges to the Shannon entropy, with the logarithm in base 2

Parameters

prob	Real probability vector
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

Returns

Renyi- α entropy, with the logarithm in base 2

6.1.3.149 reshape()

Reshape.

Uses column-major order when reshaping (same as MATLAB)

Α	Eigen expression
rows	Number of rows of the reshaped matrix
cols	Number of columns of the reshaped matrix

Reshaped matrix with rows rows and cols columns, as a dynamic matrix over the same scalar field as A

6.1.3.150 rho2bloch()

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

See also

qpp::bloch2rho()

Note

It is implicitly assumed that the density matrix is Hermitian

Parameters

A Eigen expression

Returns

3-dimensional Bloch vector

6.1.3.151 rho2pure()

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

Note

No purity check is done, the input state A must have rank one, otherwise the function returns the first non-zero eigenvector of A

Parameters

A Eigen expression, assumed to be proportional to a projector onto a pure state, i.e. A is assumed to have rank one

The unique non-zero eigenvector of A (up to a phase), as a dynamic column vector over the same scalar field as A

6.1.3.152 save()

Saves Eigen expression to a binary file (internal format) in double precision.

See also

qpp::load()

Parameters

Α	Eigen expression
fname	Output file name

6.1.3.153 saveMATLAB() [1/2]

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

qpp::loadMATLAB()

Template Parameters

Complex Eigen type

Α	Eigen expression over the complex field
---	---

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be saved
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details

6.1.3.154 saveMATLAB() [2/2]

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

qpp::loadMATLAB()

Template Parameters

Npn-complex	Eigen type
-------------	------------

Parameters

Α	Non-complex Eigen expression	
mat_file	MATALB .mat file	
var_name	Variable name in the .mat file representing the matrix to be saved	
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details	

6.1.3.155 schatten()

Schatten matrix norm.

Α	Eigen expression
p	Real number, greater or equal to 1, use qpp::infty for $p=\infty$

Schatten-p matrix norm of A

Schmidt basis on Alice side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix \boldsymbol{U} whose columns represent the Schmidt basis vectors on Alice side.

Schmidt basis on Alice side.

idx d = 2)

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix U whose columns represent the Schmidt basis vectors on Alice side.

6.1.3.158 schmidtB() [1/2] template<typename Derived > cmat qpp::schmidtB (

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & dims )
```

Schmidt basis on Bob side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

Schmidt basis on Bob side.

idx d = 2)

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.161 schmidtcoeffs() [2/2]

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.162 schmidtprobs() [1/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.3.163 schmidtprobs() [2/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.3.164 sigma()

Standard deviation.

prob	Real probability vector representing the probability distribution of X
X	Real random variable values represented by an STL-like container

Returns

Standard deviation of X

6.1.3.165 sinm()

Matrix sin.

Parameters

A Eigen expression

Returns

Matrix sine of A

6.1.3.166 spectralpowm()

Matrix power.

See also

qpp::powm()

Uses the spectral decomposition of \emph{A} to compute the matrix power. By convention $\emph{A}^0 = \emph{I}$.

Α	Eigen expression
Z	Complex number

Matrix power A^z

6.1.3.167 sqrtm()

Matrix square root.

Parameters

```
A Eigen expression
```

Returns

Matrix square root of A

6.1.3.168 sum() [1/3]

Element-wise sum of A.

Parameters

```
A Eigen expression
```

Returns

Element-wise sum of A, as a scalar over the same scalar field as A

6.1.3.169 sum() [2/3]

Element-wise sum of an STL-like range.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Element-wise sum of the range, as a scalar over the same scalar field as the range

Element-wise sum of the elements of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Element-wise sum of the elements of the container, as a scalar over the same scalar field as the container

6.1.3.171 super2choi()

Converts superoperator matrix to Choi matrix.

See also

qpp::choi2super()

Parameters

A Superoperator matrix

Returns

Choi matrix

6.1.3.172 svals()

Singular values.

Parameters

A Eigen expression

Returns

Singular values of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.173 svd()

Full singular value decomposition.

Parameters

A Eigen expression

Returns

Tuple of: 1. Left sigular vectors of A, as columns of a complex dynamic matrix, 2. Singular values of A, ordered in decreasing order, as a real dynamic column vector, and 3. Right singular vectors of A, as columns of a complex dynamic matrix

6.1.3.174 svdU()

Left singular vectors.

Parameters

```
A Eigen expression
```

Returns

Complex dynamic matrix, whose columns are the left singular vectors of A

6.1.3.175 svdV()

Right singular vectors.

Parameters

```
A Eigen expression
```

Returns

Complex dynamic matrix, whose columns are the right singular vectors of A

6.1.3.176 syspermute() [1/2]

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Parameters

Α	Eigen expression
perm	Permutation
dims	Dimensions of the multi-partite system

Returns

Permuted system, as a dynamic matrix over the same scalar field as A

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Parameters

Α	Eigen expression	
perm	Permutation	
d	Subsystem dimensions	

Returns

Permuted system, as a dynamic matrix over the same scalar field as A

6.1.3.178 TFQ()

Inverse (adjoint) qudit quantum Fourier transform.

Parameters

Α	Eigen expression	
d	Subsystem dimensions	
swap	Swaps the qubits/qudits at the end (true by default)	

Returns

Inverse (adjoint) qudit quantum Fourier transform applied on A

6.1.3.179 trace()

Trace.

Parameters

```
A Eigen expression
```

Returns

Trace of A, as a scalar over the same scalar field as A

6.1.3.180 transpose()

Transpose.

Parameters

```
A Eigen expression
```

Returns

Transpose of A, as a dynamic matrix over the same scalar field as A

```
6.1.3.181 tsallis() [1/2] template<typename Derived > double qpp::tsallis ( const Eigen::MatrixBase< Derived > & A, double q)
```

Tsallis- q entropy of the density matrix A, for $q \ge 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the von-Neumann entropy, with the logarithm in base e

Parameters

Α	Eigen expression	
q	Non-negative real number	

Returns

Tsallis- q entropy

Tsallis- q entropy of the probability distribution *prob*, for $q \ge 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the Shannon entropy, with the logarithm in base e

Parameters

prob	Real probability vector
q	Non-negative real number

Returns

Tsallis- q entropy

6.1.3.183 uniform()

```
std::vector<double> qpp::uniform (
    idx N ) [inline]
```

Uniform probability distribution vector.

Parameters

N Size of the alphabet

Returns

Real vector consisting of a uniform distribution of size N

6.1.3.184 var()

Variance.

Parameters

prob	Real probability vector representing the probability distribution of X
Χ	Real random variable values represented by an STL-like container

Returns

Variance of X

6.1.3.185 x2contfrac()

Simple continued fraction expansion.

See also

```
qpp::contfrac2x()
```

Parameters

Χ	Real number
Ν	Maximum number of terms in the expansion
cut	Stop the expansion when the next term is greater than cut

Returns

Integer vector containing the simple continued fraction expansion of x. If there are M less than N terms in the expansion, a shorter vector with M components is returned.

6.1.4 Variable Documentation

6.1.4.1 chop

```
constexpr double qpp::chop = 1e-10
```

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

6.1.4.2 ee

```
constexpr double qpp::ee = 2.718281828459045235360287471352662497
```

Base of natural logarithm, e.

6.1.4.3 eps

```
constexpr double qpp::eps = std::numeric_limits<double>::epsilon()
```

Used to decide whether a number or expression in double precision is zero or not for the purpose of a specific computation.

Example:

```
if(std::abs(x) < qpp::eps) // x is zero</pre>
```

6.1.4.4 idx_infty

```
const idx qpp::idx_infty = static_cast<idx>(-1)
```

Used to denote the largest unsigned index.

6.1.4.5 infty

```
constexpr double qpp::infty = std::numeric_limits<double>::max()
```

Used to denote infinity in double precision.

6.1.4.6 maxn

```
constexpr idx qpp::maxn = 64
```

Maximum number of allowed qubits/qudits (subsystems)

Used internally to allocate arrays on the stack (for performance reasons):

6.1.4.7 pi

```
constexpr double qpp::pi = 3.141592653589793238462643383279502884
```

 π

6.2 qpp::exception Namespace Reference

Quantum++ exception hierarchy namespace.

Classes

• class CustomException

Custom exception.

· class DimsInvalid

Invalid dimension(s) exception.

· class DimsMismatchCvector

Dimension(s) mismatch column vector size exception.

• class DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

· class DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

· class DimsMismatchVector

Dimension(s) mismatch vector size exception.

class DimsNotEqual

Dimensions not equal exception.

· class Duplicates

System (e.g. std::vector) has duplicates exception.

class Exception

Base class for generating Quantum++ custom exceptions.

class InvalidIterator

Invalid iterator.

• class MatrixMismatchSubsys

Matrix mismatch subsystems exception.

• class MatrixNotCvector

Matrix is not a column vector exception.

class MatrixNotRvector

Matrix is not a row vector exception.

class MatrixNotSquare

Matrix is not square exception.

· class MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

class MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

· class MatrixNotSquareNorVector

Matrix is not square nor vector exception.

· class MatrixNotVector

Matrix is not a vector exception.

class NoCodeword

Codeword does not exist exception.

· class NotBipartite

Not bi-partite exception.

· class NotImplemented

Code not yet implemented.

class NotQubitCvector

Column vector is not 2 x 1 exception.

class NotQubitMatrix

Matrix is not 2 x 2 exception.

· class NotQubitRvector

Row vector is not 1 x 2 exception.

class NotQubitSubsys

Subsystems are not qubits exception.

class NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

class OutOfRange

Argument out of range exception.

class PermInvalid

Invalid permutation exception.

· class PermMismatchDims

Permutation mismatch dimensions exception.

class QuditAlreadyMeasured

Qudit was already measured exception.

· class SizeMismatch

Size mismatch exception.

• class SubsysMismatchDims

Subsystems mismatch dimensions exception.

class TypeMismatch

Type mismatch exception.

class UndefinedType

Not defined for this type exception.

• class Unknown

Unknown exception.

class ZeroSize

Object has zero size exception.

6.2.1 Detailed Description

Quantum++ exception hierarchy namespace.

6.3 qpp::experimental Namespace Reference

Experimental/test functions/classes, do not use or modify.

6.3.1 Detailed Description

Experimental/test functions/classes, do not use or modify.

6.4 qpp::internal Namespace Reference

Internal utility functions, do not use them directly or modify them.

Classes

- struct Display Impl
- · class IOManipEigen
- · class IOManipPointer
- · class IOManipRange
- · class Singleton

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Functions

- void n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- $\bullet \ \ \text{template}{<} \text{typename Derived} >$

bool check_square_mat (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ \mathsf{template} \mathord{<} \mathsf{typename} \ \mathsf{Derived} >$

bool bool check_vector (const Eigen::MatrixBase Derived > &A)

• template<typename Derived >

bool check_rvector (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

bool check_cvector (const Eigen::MatrixBase< Derived > &A)

• template<typename T >

bool check_nonzero_size (const T &x) noexcept

- template<typename T1 , typename T2 >

bool check_matching_sizes (const T1 &lhs, const T2 &rhs) noexcept

- bool check_dims (const std::vector< idx > &dims)
- template<typename Derived >

 $bool\ check_dims_match_mat\ (const\ std::vector < idx > \&dims,\ const\ Eigen::MatrixBase < Derived > \&A)$

• template<typename Derived >

bool check_dims_match_cvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool check dims match rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- bool check_eq_dims (const std::vector< idx > &dims, idx dim) noexcept
- bool check_no_duplicates (std::vector< idx > v)
- bool check_subsys_match_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)

```
    template < typename Derived >
        bool check_qubit_matrix (const Eigen::MatrixBase < Derived > &A) noexcept
```

• template<typename Derived >

bool check_qubit_cvector (const Eigen::MatrixBase< Derived > &A) noexcept

template<typename Derived >
 bool check_qubit_rvector (const Eigen::MatrixBase< Derived > &A) noexcept

template<typename Derived >
 bool check_qubit_vector (const Eigen::MatrixBase< Derived > &A) noexcept

bool check_perm (const std::vector< idx > &perm)

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > kron2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::
 MatrixBase< Derived2 > &B)

template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > dirsum2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen
 ::MatrixBase< Derived2 > &B)

template<typename T >
 void variadic_vector_emplace (std::vector< T > &)

- $\begin{tabular}{ll} & \textbf{template}$<&typename T$, typename First , typename... Args>&void variadic_vector_emplace (std::vector< T>&v, First &&first, Args &&... args) \\ \end{tabular}$
- idx get num subsys (idx D, idx d)
- idx get_dim_subsys (idx sz, idx N)

6.4.1 Detailed Description

Internal utility functions, do not use them directly or modify them.

6.4.2 Function Documentation

6.4.2.1 check_cvector()

6.4.2.2 check_dims()

```
bool qpp::internal::check_dims (  const \ std::vector < \ idx \ > \ \& \ dims \ ) \quad [inline]
```

6.4.2.3 check_dims_match_cvect()

6.4.2.4 check_dims_match_mat()

6.4.2.5 check_dims_match_rvect()

6.4.2.6 check_eq_dims()

6.4.2.7 check_matching_sizes()

6.4.2.8 check_no_duplicates()

```
bool qpp::internal::check_no_duplicates ( {\tt std::vector} < {\tt idx} \, > \, v \; ) \quad [{\tt inline}]
```

```
6.4.2.9 check_nonzero_size()
template<typename T >
bool qpp::internal::check_nonzero_size (
            const T & x ) [noexcept]
6.4.2.10 check_perm()
bool qpp::internal::check_perm (
            const std::vector< idx > & perm ) [inline]
6.4.2.11 check_qubit_cvector()
template<typename Derived >
bool qpp::internal::check_qubit_cvector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.12 check_qubit_matrix()
template<typename Derived >
bool qpp::internal::check_qubit_matrix (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.13 check_qubit_rvector()
template<typename Derived >
bool qpp::internal::check_qubit_rvector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.14 check_qubit_vector()
template<typename Derived >
bool qpp::internal::check_qubit_vector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
```

```
6.4.2.15 check_rvector()
```

```
template<typename Derived >
bool qpp::internal::check_rvector (
            const Eigen::MatrixBase< Derived > & A )
6.4.2.16 check_square_mat()
template<typename Derived >
bool qpp::internal::check_square_mat (
            const Eigen::MatrixBase< Derived > & A )
6.4.2.17 check_subsys_match_dims()
bool qpp::internal::check_subsys_match_dims (
            const std::vector< idx > & subsys,
            const std::vector< idx > & dims ) [inline]
6.4.2.18 check_vector()
template<typename Derived >
bool qpp::internal::check_vector (
            const Eigen::MatrixBase< Derived > & A )
6.4.2.19 dirsum2()
template<typename Derived1 , typename Derived2 >
dyn_mat<typename Derived1::Scalar> qpp::internal::dirsum2 (
            const Eigen::MatrixBase< Derived1 > & A,
            const Eigen::MatrixBase< Derived2 > & B )
6.4.2.20 get_dim_subsys()
idx qpp::internal::get_dim_subsys (
            idx sz,
             idx N ) [inline]
```

6.4.2.21 get_num_subsys()

```
idx qpp::internal::get_num_subsys (
            idx D,
             idx d ) [inline]
6.4.2.22 kron2()
template<typename Derived1 , typename Derived2 >
dyn_mat<typename Derived1::Scalar> qpp::internal::kron2 (
            const Eigen::MatrixBase< Derived1 > & A,
             const Eigen::MatrixBase< Derived2 > & B )
6.4.2.23 multiidx2n()
idx qpp::internal::multiidx2n (
             const idx *const midx,
             idx numdims,
             const idx *const dims ) [inline], [noexcept]
6.4.2.24 n2multiidx()
void qpp::internal::n2multiidx (
             idx n,
             idx numdims,
             const idx *const dims,
             idx * result ) [inline], [noexcept]
6.4.2.25 variadic_vector_emplace() [1/2]
template<typename T >
void qpp::internal::variadic_vector_emplace (
            std::vector< T > & )
6.4.2.26 variadic_vector_emplace() [2/2]
template<typename T , typename First , typename... Args>
void qpp::internal::variadic_vector_emplace (
             std::vector< T > & v,
             First && first,
             Args &&... args )
```

6.5 qpp::literals Namespace Reference

Functions

```
• constexpr cplx operator"" _i (unsigned long long int x) noexcept \textit{User-defined literal for complex } i = \sqrt{-1} \textit{ (integer overload)}
```

```
template<char... Bits>
ket operator"" _ket ()
```

Multi-partite qubit ket user-defined literal.

template<char... Bits> bra operator"" _bra ()

Multi-partite qubit bra user-defined literal.

template<char... Bits> cmat operator"" _prj ()

Multi-partite qubit projector user-defined literal.

6.5.1 Function Documentation

```
6.5.1.1 operator"""_bra()

template<char... Bits>
bra qpp::literals::operator"" _bra ( )
```

Multi-partite qubit bra user-defined literal.

See also

```
qpp::mket() and qpp::adjoint()
```

Constructs the multi-partite qubit bra $\langle \mathrm{Bits}|$

Template Parameters

```
Bits String of binary numbers representing the qubit bra
```

Returns

Multi-partite qubit bra, as a complex dynamic row vector

User-defined literal for complex $i = \sqrt{-1}$ (integer overload)

Example:

```
cplx z = 4_i; // type of z is std::complex<double>
```

6.5.1.3 operator""" _ket()

```
template<char... Bits>
ket qpp::literals::operator"" _ket ( )
```

Multi-partite qubit ket user-defined literal.

See also

qpp::mket()

Constructs the multi-partite qubit ket $|Bits\rangle$

Template Parameters

Bits	String of binary numbers representing the qubit ket
------	---

Returns

Multi-partite qubit ket, as a complex dynamic column vector

6.5.1.4 operator""" _prj()

```
template<char... Bits>
cmat qpp::literals::operator"" _prj ( )
```

Multi-partite qubit projector user-defined literal.

See also

qpp::mprj()

Constructs the multi-partite qubit projector $|\mathrm{Bits}\rangle\langle\mathrm{Bits}|$ (in the computational basis)

Template Parameters

Bits String of binary numbers representing the qubit state to project on

\mathbf{L}	ΔT	 rn	c

Multi-partite qubit projector, as a complex dynamic matrix

Chapter 7


Class Documentation

7.1 qpp::Bit_circuit Class Reference


Classical reversible circuit simulator.

#include <classes/reversible.h>

Inheritance diagram for qpp::Bit_circuit:



Collaboration diagram for qpp::Bit_circuit:



Classes

struct Gate_count

Public Member Functions

• Bit_circuit (const Dynamic_bitset &dynamic_bitset)

Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.

Bit_circuit & X (idx pos)

Bit flip.

Bit_circuit & NOT (idx pos)

Bit flip

• Bit_circuit & CNOT (const std::vector < idx > &pos)

Controlled-NOT.

• Bit_circuit & TOF (const std::vector< idx > &pos)

Toffoli gate.

Bit_circuit & SWAP (const std::vector < idx > &pos)

Swap bits.

• Bit_circuit & FRED (const std::vector< idx > &pos)

Fredkin gate (Controlled-SWAP)

• Bit_circuit & reset () noexcept

Reset the circuit all zero, clear all gates.

• Dynamic_bitset (idx N)

Inherited constructor.

Public Attributes

struct qpp::Bit_circuit::Gate_count gate_count
 Gate counters.

Additional Inherited Members

7.1.1 Detailed Description

Classical reversible circuit simulator.

7.1.2 Constructor & Destructor Documentation

7.1.2.1 Bit_circuit()

Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.

Parameters

7.1.3 Member Function Documentation

7.1.3.1 CNOT()

Controlled-NOT.

Parameters

```
pos Bit position in the circuit
```

Returns

Reference to the current instance

7.1.3.2 Dynamic_bitset()

```
qpp::Dynamic_bitset::Dynamic_bitset [inline], [explicit]
```

Inherited constructor.

7.1.3.3 FRED()

Fredkin gate (Controlled-SWAP)

Parameters

pos Bit positions in the circuit, in the order control-target-target

Returns

Reference to the current instance

7.1.3.4 NOT()

```
Bit_circuit& qpp::Bit_circuit::NOT (
        idx pos ) [inline]
```

Bit flip.

See also

qpp::Bit_circuit::X()

Parameters

pos Bit position in the circuit

Returns

Reference to the current instance

7.1.3.5 reset()

```
Bit_circuit& qpp::Bit_circuit::reset ( ) [inline], [noexcept]
```

Reset the circuit all zero, clear all gates.

Returns

Reference to the current instance

7.1.3.6 SWAP()

Swap bits.

Parameters

pos Bit positions in the circuit

Returns

Reference to the current instance

7.1.3.7 TOF()

Toffoli gate.

Parameters

pos | Bit positions in the circuit, in the order control-control-target

Returns

Reference to the current instance

7.1.3.8 X()

```
Bit_circuit& qpp::Bit_circuit::X (
        idx pos ) [inline]
```

Bit flip.

See also

qpp::Bit_circuit::NOT()

Parameters

pos Bit position in the circuit

Returns

Reference to the current instance

7.1.4 Member Data Documentation

7.1.4.1 gate_count

```
struct qpp::Bit_circuit::Gate_count qpp::Bit_circuit::gate_count
```

Gate counters.

The documentation for this class was generated from the following file:


• classes/reversible.h

7.2 qpp::Codes Class Reference


const Singleton class that defines quantum error correcting codes

```
#include <classes/codes.h>
```

Inheritance diagram for qpp::Codes:



Collaboration diagram for qpp::Codes:



Public Types

• enum Type { Type::FIVE_QUBIT = 1, Type::SEVEN_QUBIT_STEANE, Type::NINE_QUBIT_SHOR }

Code types, add more codes here if needed.

Public Member Functions

ket codeword (Type type, idx i) const
 Returns the codeword of the specified code type.

Private Member Functions

• Codes ()

Default constructor.

Default destructor.

• \sim Codes ()=default

Friends

class internal::Singleton < const Codes >

Additional Inherited Members

7.2.1 Detailed Description

const Singleton class that defines quantum error correcting codes

7.2.2 Member Enumeration Documentation

7.2.2.1 Type

```
enum qpp::Codes::Type [strong]
```

Code types, add more codes here if needed.

See also

```
qpp::Codes::codeword()
```

Enumerator

FIVE_QUBIT	[[5,1,3]] qubit code
SEVEN_QUBIT_STEANE	[[7,1,3]] Steane qubit code
NINE_QUBIT_SHOR	[[9,1,3]] Shor qubit code

7.2.3 Constructor & Destructor Documentation

7.2.3.1 Codes()

```
qpp::Codes::Codes ( ) [inline], [private]
```

Default constructor.

7.2.3.2 ∼Codes()

```
qpp::Codes::~Codes ( ) [private], [default]
```

Default destructor.

7.2.4 Member Function Documentation

7.2.4.1 codeword()

Returns the codeword of the specified code type.

See also

qpp::Codes::Type

Parameters

type	Code type
i	Codeword index

Returns

i-th codeword of the code type

7.2.5 Friends And Related Function Documentation

7.2.5.1 internal::Singleton < const Codes >

```
friend class internal::Singleton< const Codes > [friend]
```

The documentation for this class was generated from the following file:


classes/codes.h

7.3 qpp::exception::CustomException Class Reference


Custom exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::CustomException:



Collaboration diagram for qpp::exception::CustomException:



Public Member Functions

· CustomException (const std::string &where, const std::string &what)

Private Member Functions

std::string type_description () const override
 Exception type description.

Private Attributes

std::string what_{{}}

7.3.1 Detailed Description

Custom exception.

Custom exception, the user must provide a custom message

7.3.2 Constructor & Destructor Documentation

7.3.2.1 CustomException()

7.3.3 Member Function Documentation

7.3.3.1 type_description()

```
std::string qpp::exception::CustomException::type_description ( ) const [inline], [override],
[private], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

7.3.4 Member Data Documentation

7.3.4.1 what_

```
std::string qpp::exception::CustomException::what_ {} [private]
```

The documentation for this class was generated from the following file:


· classes/exception.h

7.4 qpp::exception::DimsInvalid Class Reference


Invalid dimension(s) exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsInvalid:



Collaboration diagram for qpp::exception::DimsInvalid:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.4.1 Detailed Description

Invalid dimension(s) exception.

std::vector<idx> of dimensions has zero size or contains zeros

7.4.2 Member Function Documentation

7.4.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.4.2.2 type_description()

std::string qpp::exception::DimsInvalid::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.5 qpp::exception::DimsMismatchCvector Class Reference


Dimension(s) mismatch column vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchCvector:



Collaboration diagram for qpp::exception::DimsMismatchCvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.5.1 Detailed Description

Dimension(s) mismatch column vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a column vector)

7.5.2 Member Function Documentation

7.5.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred
--

7.5.2.2 type_description()

std::string qpp::exception::DimsMismatchCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.6 qpp::exception::DimsMismatchMatrix Class Reference


Dimension(s) mismatch matrix size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchMatrix:



Collaboration diagram for qpp::exception::DimsMismatchMatrix:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.6.1 Detailed Description

Dimension(s) mismatch matrix size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of rows of the Eigen::Matrix (assumed to be a square matrix)

7.6.2 Member Function Documentation

7.6.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred
--

7.6.2.2 type_description()

```
std::string qpp::exception::DimsMismatchMatrix::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.7 qpp::exception::DimsMismatchRvector Class Reference


Dimension(s) mismatch row vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchRvector:



Collaboration diagram for qpp::exception::DimsMismatchRvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.7.1 Detailed Description

Dimension(s) mismatch row vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row vector)

7.7.2 Member Function Documentation

7.7.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

Text representing where the exception of	d
--	---

7.7.2.2 type_description()

std::string qpp::exception::DimsMismatchRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.8 qpp::exception::DimsMismatchVector Class Reference


Dimension(s) mismatch vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchVector:



Collaboration diagram for qpp::exception::DimsMismatchVector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.8.1 Detailed Description

Dimension(s) mismatch vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row/column vector)

7.8.2 Member Function Documentation

7.8.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
******	Toxt representing where the exception eccurred

7.8.2.2 type_description()

```
std::string qpp::exception::DimsMismatchVector::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.9 qpp::exception::DimsNotEqual Class Reference


Dimensions not equal exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsNotEqual:



Collaboration diagram for qpp::exception::DimsNotEqual:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.9.1 Detailed Description

Dimensions not equal exception.

Local/global dimensions are not equal

7.9.2 Member Function Documentation

7.9.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.9.2.2 type_description()

std::string qpp::exception::DimsNotEqual::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

· classes/exception.h

7.10 qpp::internal::Display_Impl_ Struct Reference

```
#include <internal/util.h>
```

Inheritance diagram for qpp::internal::Display_Impl_:



Public Member Functions

template<typename T >
 std::ostream & display_impl_ (const T &A, std::ostream &os, double chop=qpp::chop) const

7.10.1 Member Function Documentation

7.10.1.1 display_impl_()

The documentation for this struct was generated from the following file:


• internal/util.h

7.11 qpp::exception::Duplicates Class Reference


System (e.g. std::vector) has duplicates exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Duplicates:



Collaboration diagram for qpp::exception::Duplicates:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.11.1 Detailed Description

System (e.g. std::vector) has duplicates exception.

7.11.2 Member Function Documentation

7.11.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.11.2.2 type_description()

```
std::string qpp::exception::Duplicates::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.12 qpp::Dynamic_bitset Class Reference


Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std:bitset < N >)

#include <classes/reversible.h>

Inheritance diagram for qpp::Dynamic_bitset:



Collaboration diagram for qpp::Dynamic_bitset:



Public Types

- using value_type = unsigned int
 Type of the storage elements.
- using storage_type = std::vector< value_type >
 Type of the storage.

Public Member Functions

• Dynamic bitset (idx N)

Constructor, initializes all bits to false (zero)

virtual ~Dynamic bitset ()=default

Default virtual destructor.

const storage_type & data () const

Raw storage space of the bitset.

• idx size () const noexcept

Number of bits stored in the bitset.

• idx storage_size () const noexcept

Size of the underlying storage space (in units of value_type, unsigned int by default)

· idx count () const noexcept

Number of bits set to one in the bitset (Hamming weight)

bool get (idx pos) const noexcept

The value of the bit at position pos.

· bool none () const noexcept

Checks whether none of the bits are set.

• bool all () const noexcept

Checks whether all bits are set.

• bool any () const noexcept

Checks whether any bit is set.

Dynamic_bitset & set (idx pos, bool value=true)

Sets the bit at position pos.

Dynamic_bitset & set () noexcept

Set all bits to true.

• Dynamic bitset & rand (idx pos, double p=0.5)

Sets the bit at position pos according to a Bernoulli(p) distribution.

• Dynamic_bitset & rand (double p=0.5)

Sets all bits according to a Bernoulli(p) distribution.

Dynamic_bitset & reset (idx pos)

Sets the bit at position pos to false.

Dynamic_bitset & reset () noexcept

Sets all bits to false.

Dynamic_bitset & flip (idx pos)

Flips the bit at position pos.

· Dynamic bitset & flip () noexcept

Flips all bits.

• bool operator== (const Dynamic_bitset &rhs) const noexcept

Equality operator.

• bool operator!= (const Dynamic_bitset &rhs) const noexcept

Inequality operator.

• idx operator- (const Dynamic_bitset &rhs) const noexcept

Number of places the two bitsets differ (Hamming distance)

template < class CharT = char, class Traits = std::char_traits < CharT>, class Allocator = std::allocator < CharT>> std::basic_string < CharT, Traits, Allocator > to_string (CharT zero=CharT('0'), CharT one=CharT('1')) const String representation.

Protected Member Functions

- idx index_ (idx pos) const
 Index of the pos bit in the storage space.
- idx offset_ (idx pos) const

Offset of the pos bit in the storage space relative to its index.

Protected Attributes

```
• idx storage_size_
Storage size.
```

idx N

Number of bits.

std::vector< value_type > v_
 Storage space.

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display()* override, displays the bitset bit by bit

7.12.1 Detailed Description

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

7.12.2 Member Typedef Documentation

```
7.12.2.1 storage_type
```

```
using qpp::Dynamic_bitset::storage_type = std::vector<value_type>
```

Type of the storage.

7.12.2.2 value_type

```
using qpp::Dynamic_bitset::value_type = unsigned int
```

Type of the storage elements.

7.12.3 Constructor & Destructor Documentation

7.12.3.1 Dynamic_bitset()

Constructor, initializes all bits to false (zero)

Parameters

N Number of bits in the bitset

```
7.12.3.2 ~Dynamic_bitset()
```

```
virtual qpp::Dynamic_bitset::~Dynamic_bitset ( ) [virtual], [default]
```

Default virtual destructor.

7.12.4 Member Function Documentation

```
7.12.4.1 all()
```

```
bool qpp::Dynamic_bitset::all ( ) const [inline], [noexcept]
```

Checks whether all bits are set.

Returns

True if all of the bits are set

7.12.4.2 any()

```
bool qpp::Dynamic_bitset::any ( ) const [inline], [noexcept]
```

Checks whether any bit is set.

Returns

True if any of the bits is set

7.12.4.3 count()

```
idx qpp::Dynamic_bitset::count ( ) const [inline], [noexcept]
```

Number of bits set to one in the bitset (Hamming weight)

Returns

Hamming weight

7.12.4.4 data()

```
const storage_type& qpp::Dynamic_bitset::data ( ) const [inline]
```

Raw storage space of the bitset.

Returns

Const reference to the underlying storage space

7.12.4.5 display()

qpp::IDisplay::display() override, displays the bitset bit by bit

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.12.4.6 flip() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip (
        idx pos ) [inline]
```

Flips the bit at position pos.

Parameters

pos Position in the bitset

Returns

Reference to the current instance

```
7.12.4.7 flip() [2/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip ( ) [inline], [noexcept]
```

Flips all bits.

Returns

Reference to the current instance

7.12.4.8 get()

```
bool qpp::Dynamic_bitset::get (
          idx pos ) const [inline], [noexcept]
```

The value of the bit at position pos.

Parameters

pos	Position in the bitset
-----	------------------------

Returns

The value of the bit at position pos

7.12.4.9 index_()

Index of the pos bit in the storage space.

Parameters

```
pos Bit location
```

Returns

Index of the pos bit in the storage space

7.12.4.10 none()

```
bool qpp::Dynamic_bitset::none ( ) const [inline], [noexcept]
```

Checks whether none of the bits are set.

Returns

True if none of the bits are set

7.12.4.11 offset_()

Offset of the *pos* bit in the storage space relative to its index.

Parameters

```
pos Bit location
```

Returns

Offset of the pos bit in the storage space relative to its index

7.12.4.12 operator"!=()

Inequality operator.

Parameters

```
rhs Dynamic_bitset against which the inequality is being tested
```

Returns

True if the bitsets are not equal (bit by bit), false otherwise

7.12.4.13 operator-()

Number of places the two bitsets differ (Hamming distance)

Parameters

```
rhs Dynamic_bitset against which the Hamming distance is computed
```

Returns

Hamming distance

7.12.4.14 operator==()

Equality operator.

Parameters

```
rhs Dynamic_bitset against which the equality is being tested
```

Returns

True if the bitsets are equal (bit by bit), false otherwise

7.12.4.15 rand() [1/2]

```
Dynamic_bitset& qpp::Dynamic_bitset::rand (
    idx pos,
    double p = 0.5 ) [inline]
```

Sets the bit at position *pos* according to a Bernoulli(p) distribution.

Parameters

pos	Position in the bitset
р	Probability

Returns

Reference to the current instance

Sets all bits according to a Bernoulli(p) distribution.

Parameters

```
p Probability
```

Returns

Reference to the current instance

Sets the bit at position pos to false.

Parameters

```
pos Position in the bitset
```

Returns

Reference to the current instance

```
7.12.4.18 reset() [2/2]
Dynamic_bitset& qpp::Dynamic_bitset::reset ( ) [inline], [noexcept]
Sets all bits to false.
```

Returns

Reference to the current instance

```
7.12.4.19 set() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::set (
        idx pos,
        bool value = true ) [inline]
```

Sets the bit at position pos.

Parameters

pos	Position in the bitset
value	Bit value

Returns

Reference to the current instance

```
7.12.4.20 set() [2/2]
Dynamic_bitset& qpp::Dynamic_bitset::set ( ) [inline], [noexcept]
```

Set all bits to true.

Returns

Reference to the current instance

```
7.12.4.21 size()
```

```
idx qpp::Dynamic_bitset::size ( ) const [inline], [noexcept]
```

Number of bits stored in the bitset.

Returns

Number of bits stored in the bitset

```
7.12.4.22 storage_size()
```

```
idx qpp::Dynamic_bitset::storage_size ( ) const [inline], [noexcept]
```

Size of the underlying storage space (in units of value_type, unsigned int by default)

Returns

Size of the underlying storage space

7.12.4.23 to_string()

String representation.

Template Parameters

CharT	String character type
Traits	String traits
Allocator	String Allocator

Parameters

	Character representing the zero
one	Character representing the one

Returns

The bitset as a string

7.12.5 Member Data Documentation

```
7.12.5.1 N_
```

```
idx qpp::Dynamic_bitset::N_ [protected]
```

Number of bits.


7.12.5.2 storage_size_

```
idx qpp::Dynamic_bitset::storage_size_ [protected]
```

Storage size.

166	Class Documentation
7.12.5.3 v_	
<pre>std::vector<value_type> qpp::Dynamic_bitset::v_ [protected]</value_type></pre>	
Storage space.	
The documentation for this class was generated from the following file:	
• classes/reversible.h	
7.13 qpp::exception::Exception Class Reference	
Base class for generating Quantum++ custom exceptions.	
<pre>#include <classes exception.h=""></classes></pre>	

Inheritance diagram for qpp::exception::Exception:



Collaboration diagram for qpp::exception::Exception:



Public Member Functions

• Exception (const std::string &where)

Constructs an exception.

- virtual const char * what () const noexcept override

Overrides std::exception::what()

• virtual std::string type_description () const =0

Exception type description.

Private Attributes

- std::string where_
- std::string msg_

7.13.1 Detailed Description

Base class for generating Quantum++ custom exceptions.

Derive from this class if more exceptions are needed, making sure to override qpp::exception::Exception::type_description() in the derived class and to inherit the constructor qpp::exception::Exception::Exception(). Preferably keep your newly defined exception classes in the namespace qpp::exception.

Example:

7.13.2 Constructor & Destructor Documentation

7.13.2.1 Exception()

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.13.3 Member Function Documentation

7.13.3.1 type_description()

```
std::string qpp::exception::Exception::type_description ( ) const [inline], [pure virtual]
```

Exception type description.

Returns

Exception type description

Implemented in qpp::exception::InvalidIterator, qpp::exception::NotImplemented, qpp::exception::CustomException, qpp::exception::Duplicates, qpp::exception::QuditAlreadyMeasured, qpp::exception::UndefinedType, qpp::exception::SizeMismatch, qpp::exception::TypeMismatch, qpp::exception::OutOfRange, qpp::exception::NotOdeword, qpp::exception::NotBipartite, qpp::exception::NotQubitSubsys, qpp::exception::NotQubitVector, qpp::exception::NotQubitRvector, qpp::exception::NotQubitCvector qpp::exception::NotQubitMatrix, qpp::exception::PermMismatchDims, qpp::exception::PermInvalid, qpp::exception::SubsysMismatchEqpp::exception::DimsMismatchVector, qpp::exception::DimsMismatchCvector, qpp::exception::DimsMismatchMatrix, qpp::exception::DimsNotEqual, qpp::exception::DimsInvalid, qpp::exception::MatrixMismatchSu qpp::exception::MatrixNotSquareNorVector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::Unknown.

7.13.3.2 what()

virtual const char* qpp::exception::Exception::what () const [inline], [override], [virtual],
[noexcept]

Overrides std::exception::what()

Returns

Exception description

7.13.4 Member Data Documentation

```
7.13.4.1 msg_
```

std::string qpp::exception::Exception::msg_ [mutable], [private]

7.13.4.2 where_

std::string qpp::exception::Exception::where_ [private]

The documentation for this class was generated from the following file:

· classes/exception.h

7.14 qpp::Bit_circuit::Gate_count Struct Reference

```
#include <classes/reversible.h>
```

Public Attributes

- idx NOT = 0
- idx & X = NOT
- idx CNOT = 0
- idx SWAP = 0
- idx FRED = 0
- idx TOF = 0

7.14.1 Member Data Documentation

7.14.1.1 CNOT

```
idx qpp::Bit_circuit::Gate_count::CNOT = 0
```

7.14.1.2 FRED

```
idx qpp::Bit_circuit::Gate_count::FRED = 0
```

7.14.1.3 NOT

```
idx qpp::Bit_circuit::Gate_count::NOT = 0
```

7.14.1.4 SWAP

```
idx qpp::Bit_circuit::Gate_count::SWAP = 0
```

7.14.1.5 TOF

```
idx qpp::Bit_circuit::Gate_count::TOF = 0
```

7.14.1.6 X

```
idx& qpp::Bit_circuit::Gate_count::X = NOT
```

The documentation for this struct was generated from the following file:


• classes/reversible.h

7.15 qpp::Gates Class Reference


const Singleton class that implements most commonly used gates

#include <classes/gates.h>

Inheritance diagram for qpp::Gates:



Collaboration diagram for qpp::Gates:



Public Member Functions

- cmat Rn (double theta, const std::vector< double > &n) const
 Qubit rotation of theta about the 3-dimensional real (unit) vector n.
- cmat RX (double theta) const

Qubit rotation of theta about the X axis.

• cmat RY (double theta) const

Qubit rotation of theta about the Y axis.

cmat RZ (double theta) const

Qubit rotation of theta about the Z axis.

• cmat Zd (idx D=2) const

Generalized Z gate for qudits.

```
• cmat SWAPd (idx D=2) const
          SWAP gate for qudits.
    • cmat Fd (idx D=2) const
          Quantum Fourier transform gate for qudits.

    cmat MODMUL (idx a, idx N, idx n) const

          Modular multiplication gate for qubits Implements |x\rangle \longrightarrow |ax \bmod N\rangle.

    cmat Xd (idx D=2) const

          Generalized X gate for qudits.
    • template<typename Derived = Eigen::MatrixXcd>
      Derived Id (idx D=2) const
          Identity gate.

    template<typename Derived >

      dyn mat< typename Derived::Scalar > CTRL (const Eigen::MatrixBase< Derived > &A, const std::vector<
      idx > &ctrl, const std::vector < idx > &target, idx n, idx d=2) const
          Generates the multi-partite multiple-controlled-A gate in matrix form.

    template<typename Derived >

      dyn mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
      std::vector < idx > &dims) const
          Expands out.

    template<typename Derived >

      dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
      std::initializer list< idx > &dims) const
          Expands out.

    template<typename Derived >

      dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, idx n,
      idx d=2) const
          Expands out.
    • std::string get_name (const cmat &U) const
          Get the name of the most common qubit gates.
Public Attributes
    cmat Id2 {cmat::Identity(2, 2)}
          Identity gate.

    cmat H {cmat::Zero(2, 2)}

          Hadamard gate.
    cmat X {cmat::Zero(2, 2)}
          Pauli Sigma-X gate.

    cmat Y {cmat::Zero(2, 2)}

          Pauli Sigma-Y gate.

    cmat Z {cmat::Zero(2, 2)}

          Pauli Sigma-Z gate.

    cmat S {cmat::Zero(2, 2)}

          S gate.

    cmat T {cmat::Zero(2, 2)}

          T gate.

    cmat CNOT {cmat::Identity(4, 4)}

          Controlled-NOT control target gate.

    cmat CZ {cmat::Identity(4, 4)}

          Controlled-Phase gate.

    cmat CNOTba {cmat::Zero(4, 4)}
```

```
Controlled-NOT target->control gate.
```

• cmat SWAP {cmat::Identity(4, 4)}

SWAP gate.

• cmat TOF {cmat::ldentity(8, 8)}

Toffoli gate.

• cmat FRED {cmat::ldentity(8, 8)}

Fredkin gate.

Private Member Functions

• Gates ()

Initializes the gates.

∼Gates ()=default

Default destructor.

Friends

class internal::Singleton < const Gates >

Additional Inherited Members

7.15.1 Detailed Description

const Singleton class that implements most commonly used gates

7.15.2 Constructor & Destructor Documentation

```
7.15.2.1 Gates()
```

```
qpp::Gates::Gates ( ) [inline], [private]
```

Initializes the gates.

7.15.2.2 \sim Gates()

```
qpp::Gates::\sim Gates ( ) [private], [default]
```

Default destructor.

7.15.3 Member Function Documentation

7.15.3.1 CTRL()

Generates the multi-partite multiple-controlled-A gate in matrix form.

See also

```
qpp::applyCTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
n	Total number of subsystems
d	Subsystem dimensions

Returns

CTRL-A gate, as a matrix over the same scalar field as A

7.15.3.2 expandout() [1/3]

Expands out.

See also

```
qpp::kron()
```

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

	Α	Eigen expression
	pos	Position
ĺ	dims	Dimensions of the multi-partite system

Returns

Tensor product $I\otimes\cdots\otimes I\otimes A\otimes I\otimes\cdots\otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

```
7.15.3.3 expandout() [2/3]
```

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Note

The std::initializer_list overload exists because otherwise, in the degenerate case when *dims* has only one element, the one element list is implicitly converted to the element's underlying type, i.e. qpp::idx, which has the net effect of picking the wrong (non-vector) qpp::expandout() overload

Parameters

Α	Eigen expression
pos	Position
dims	Dimensions of the multi-partite system

Returns

Tensor product $I\otimes\cdots\otimes I\otimes A\otimes I\otimes\cdots\otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.15.3.4 expandout() [3/3]

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

Α	Eigen expression
pos	Position
n	Number of subsystems
d	Subsystem dimensions

Returns

Tensor product $I \otimes \cdots \otimes I \otimes A \otimes I \otimes \cdots \otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.15.3.5 Fd()

```
cmat qpp::Gates::Fd (
    idx D = 2 ) const [inline]
```

Quantum Fourier transform gate for qudits.

Note

Defined as
$$F = \sum_{j,k=0}^{D-1} \exp(2\pi \mathrm{i} jk/D) |j\rangle\langle k|$$

Parameters

D Dimension of the Hilbert space

Returns

Fourier transform gate for qudits

7.15.3.6 get_name()

Get the name of the most common qubit gates.

Note

Assumes that the gate U is represented by a square matrix. If not, returns the empty string

Parameters

U | Complex matrix representing the quantum gate

Returns

The name of the gate (if any), otherwise the empty string

7.15.3.7 ld()

```
template<typename Derived = Eigen::MatrixXcd>
Derived qpp::Gates::Id (
    idx D = 2 ) const [inline]
```

Identity gate.

Note

Can change the return type from complex matrix (default) by explicitly specifying the template parameter

Parameters

D Dimension of the Hilbert space

Returns

Identity gate on a Hilbert space of dimension D

7.15.3.8 MODMUL()

```
cmat qpp::Gates::MODMUL (
    idx a,
```

```
idx N, idx n) const [inline]
```

Modular multiplication gate for qubits Implements $|x\rangle \longrightarrow |ax \bmod N\rangle$.

Note

For the gate to be unitary, *a* and *N* should be co-prime. The function does not check co-primality in release versions!

The number of qubits required to implement the gate should satisfy $n \geq \lceil \log_2(N) \rceil$

Parameters

а	Positive integer less than N
Ν	Positive integer
n	Number of qubits required for implementing the gate

Returns

Modular multiplication gate

7.15.3.9 Rn()

Qubit rotation of *theta* about the 3-dimensional real (unit) vector *n*.

Parameters

theta	Rotation angle
n	3-dimensional real (unit) vector

Returns

Rotation gate

7.15.3.10 RX()

Qubit rotation of theta about the X axis.

Parameters

theta	Rotation angle
-------	----------------

Returns

Rotation gate

7.15.3.11 RY()

Qubit rotation of *theta* about the Y axis.

Parameters

Returns

Rotation gate

7.15.3.12 RZ()

Qubit rotation of theta about the Z axis.

Parameters

```
theta Rotation angle
```

Returns

Rotation gate

7.15.3.13 SWAPd()

```
cmat qpp::Gates::SWAPd (
        idx D = 2 ) const [inline]
```

SWAP gate for qudits.

Parameters

D Dimension of the Hilbert space

Returns

SWAP gate for qudits

7.15.3.14 Xd()

```
cmat qpp::Gates::Xd (
    idx D = 2 ) const [inline]
```

Generalized X gate for qudits.

Note

```
Defined as X=\sum_{j=0}^{D-1}|j\oplus 1\rangle\langle j|, i.e. raising operator X|j\rangle=|j\oplus 1\rangle
```

Parameters

D Dimension of the Hilbert space

Returns

Generalized X gate for qudits

7.15.3.15 Zd()

```
cmat qpp::Gates::Zd (
    idx D = 2 ) const [inline]
```

Generalized Z gate for qudits.

Note

Defined as
$$Z = \sum_{j=0}^{D-1} \exp(2\pi \mathrm{i} j/D) |j\rangle\langle j|$$

Parameters

D Dimension of the Hilbert space

Returns

Generalized Z gate for qudits

7.15.4 Friends And Related Function Documentation

```
7.15.4.1 internal::Singleton < const Gates >
friend class internal::Singleton < const Gates > [friend]
```

7.15.5 Member Data Documentation

```
7.15.5.1 CNOT
```

```
cmat qpp::Gates::CNOT {cmat::Identity(4, 4)}
```

Controlled-NOT control target gate.

7.15.5.2 CNOTba

```
cmat qpp::Gates::CNOTba {cmat::Zero(4, 4)}
```

Controlled-NOT target->control gate.

7.15.5.3 CZ

```
cmat qpp::Gates::CZ {cmat::Identity(4, 4)}
```

Controlled-Phase gate.

7.15.5.4 FRED

```
cmat qpp::Gates::FRED {cmat::Identity(8, 8)}
```

Fredkin gate.

```
7.15.5.5 H
cmat qpp::Gates::H {cmat::Zero(2, 2)}
Hadamard gate.
7.15.5.6 ld2
cmat qpp::Gates::Id2 {cmat::Identity(2, 2)}
Identity gate.
7.15.5.7 S
cmat qpp::Gates::S {cmat::Zero(2, 2)}
S gate.
7.15.5.8 SWAP
cmat qpp::Gates::SWAP {cmat::Identity(4, 4)}
SWAP gate.
7.15.5.9 T
cmat qpp::Gates::T {cmat::Zero(2, 2)}
T gate.
7.15.5.10 TOF
cmat qpp::Gates::TOF {cmat::Identity(8, 8)}
Toffoli gate.
```

7.15.5.11 X

```
cmat qpp::Gates::X {cmat::Zero(2, 2)}
```

Pauli Sigma-X gate.

7.15.5.12 Y

```
cmat qpp::Gates::Y {cmat::Zero(2, 2)}
```

Pauli Sigma-Y gate.

7.15.5.13 Z

```
cmat qpp::Gates::Z {cmat::Zero(2, 2)}
```

Pauli Sigma-Z gate.


The documentation for this class was generated from the following file:

· classes/gates.h

7.16 qpp::QCircuitDescription::GateStep Struct Reference

One step consisting only of gates/operators in the circuit.

 $Collaboration\ diagram\ for\ qpp:: QCircuit Description:: Gate Step:$



Public Member Functions

• GateStep ()=default

Default constructor.

GateStep (GateType gate_type, const cmat &gate, const std::vector< idx > &ctrl, const std::vector< idx > &target, idx step_no, std::string name="")

Constructs a gate step instance.

Public Attributes

```
    GateType gate_type_ = GateType::NONE
        gate type
    cmat gate_
        gate
    std::vector < idx > ctrl_
        control
    std::vector < idx > target_
        target where the gate is applied
    idx step_no_
        step number
    std::string name_
        custom name of the step
```

7.16.1 Detailed Description

One step consisting only of gates/operators in the circuit.

7.16.2 Constructor & Destructor Documentation

std::string name = """) [inline], [explicit]

Constructs a gate step instance.

Parameters

gate_type	Gate type
gate	Quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes
step_no	Circuit step number
name	Optional gate name

7.16.3 Member Data Documentation

```
7.16.3.1 ctrl_
std::vector<idx> qpp::QCircuitDescription::GateStep::ctrl_
control
7.16.3.2 gate_
cmat qpp::QCircuitDescription::GateStep::gate_
gate
7.16.3.3 gate_type_
GateType qpp::QCircuitDescription::GateStep::gate_type_ = GateType::NONE
gate type
7.16.3.4 name_
std::string qpp::QCircuitDescription::GateStep::name_
```

custom name of the step

7.16.3.5 step_no_

idx qpp::QCircuitDescription::GateStep::step_no_

step number

7.16.3.6 target_

std::vector<idx> qpp::QCircuitDescription::GateStep::target_

target where the gate is applied

The documentation for this struct was generated from the following file:


· classes/circuits.h

7.17 qpp::IDisplay Class Reference

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

#include <classes/idisplay.h>

Inheritance diagram for qpp::IDisplay:



Public Member Functions

• IDisplay ()=default

Default constructor.

IDisplay (const IDisplay &)=default

Default copy constructor.

• IDisplay (IDisplay &&)=default

Default move constructor.

IDisplay & operator= (const IDisplay &)=default

Default copy assignment operator.

IDisplay & operator= (IDisplay &&)=default

Default move assignment operator.

virtual ∼IDisplay ()=default

Default virtual destructor.

Private Member Functions

virtual std::ostream & display (std::ostream &os) const =0
 Must be overridden by all derived classes.

Friends

std::ostream & operator<< (std::ostream &os, const IDisplay &rhs)
 Overloads the extraction operator.

7.17.1 Detailed Description

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

This class defines friend inline std::ostream& operator<< (std::ostream& os, const qpp::IDisplay& rhs). The latter delegates the work to the pure private virtual function qpp::IDisplay::display() which has to be overridden by all derived classes.

7.17.2 Constructor & Destructor Documentation

```
7.17.2.1 | IDisplay() [1/3]

qpp::IDisplay::IDisplay ( ) [default]
```

Default constructor.

Default move constructor.

```
7.17.2.4 \simIDisplay() virtual qpp::IDisplay::\simIDisplay ( ) [virtual], [default]
```

Default virtual destructor.

7.17.3 Member Function Documentation

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implemented in qpp::IQCircuit, qpp::QCircuitDescription, qpp::Dynamic_bitset, qpp::QCircuitDescription::iterator::value_type_, qpp::internal::IOManipEigen, qpp::Timer< T, CLOCK_T >, qpp::internal::IOManipPointer< PointerType >, and qpp::internal::IOManipRange< InputIterator >.

Default copy assignment operator.

```
7.17.3.3 operator=() [2/2]
```

Default move assignment operator.

7.17.4 Friends And Related Function Documentation

7.17.4.1 operator <<

Overloads the extraction operator.

Delegates the work to the virtual function qpp::IDisplay::display()

The documentation for this class was generated from the following file:


· classes/idisplay.h

7.18 qpp::Init Class Reference


const Singleton class that performs additional initializations/cleanups

```
#include <classes/init.h>
```

Inheritance diagram for qpp::Init:



Collaboration diagram for qpp::Init:



Private Member Functions

• Init ()

Additional initializations.

• ∼Init ()

Cleanups.

Friends

- class internal::Singleton < const Init >

Additional Inherited Members

7.18.1 Detailed Description

const Singleton class that performs additional initializations/cleanups

7.18.2 Constructor & Destructor Documentation

```
7.18.2.1 Init()
```

```
qpp::Init::Init ( ) [inline], [private]
```

Additional initializations.

```
7.18.2.2 ∼Init()
```

```
qpp::Init::~Init ( ) [inline], [private]
```

Cleanups.

7.18.3 Friends And Related Function Documentation

7.18.3.1 internal::Singleton < const Init >

```
friend class internal::Singleton< const Init > [friend]
```

The documentation for this class was generated from the following file:


· classes/init.h

7.19 qpp::exception::InvalidIterator Class Reference


Invalid iterator.

```
#include <classes/exception.h>
```

 $Inheritance\ diagram\ for\ qpp::exception::InvalidIterator:$



Collaboration diagram for qpp::exception::InvalidIterator:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.19.1 Detailed Description

Invalid iterator.

7.19.2 Member Function Documentation

7.19.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.19.2.2 type_description()

std::string qpp::exception::InvalidIterator::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

· classes/exception.h


7.20 qpp::internal::IOManipEigen Class Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipEigen:



Collaboration diagram for qpp::internal::IOManipEigen:



Public Member Functions

- template<typename Derived > IOManipEigen (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
- IOManipEigen (const cplx z, double chop=qpp::chop)

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- cmat A_
- double chop_

7.20.1 Constructor & Destructor Documentation

```
7.20.1.1 IOManipEigen() [1/2]
```

7.20.1.2 IOManipEigen() [2/2]

7.20.2 Member Function Documentation

7.20.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.20.3 Member Data Documentation

7.20.3.1 A_

```
cmat qpp::internal::IOManipEigen::A_ [private]
```

7.20.3.2 chop_

```
double qpp::internal::IOManipEigen::chop_ [private]
```


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


7.21 qpp::internal::IOManipPointer< PointerType > Class Template Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipPointer< PointerType >:



Collaboration diagram for qpp::internal::IOManipPointer< PointerType >:



Public Member Functions

- IOManipPointer (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")
- IOManipPointer (const IOManipPointer &)=default
- IOManipPointer & operator= (const IOManipPointer &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

```
const PointerType * p_
idx N_
std::string separator_
std::string start_
std::string end_
```

7.21.1 Constructor & Destructor Documentation

7.21.2 Member Function Documentation

7.21.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.21.2.2 operator=()

7.21.3 Member Data Documentation

```
7.21.3.1 end
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::end_ [private]
7.21.3.2 N_
template<typename PointerType>
idx qpp::internal::IOManipPointer< PointerType >::N_ [private]
7.21.3.3 p_
template<typename PointerType>
const PointerType* qpp::internal::IOManipPointer< PointerType >::p_ [private]
7.21.3.4 separator_
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::separator_ [private]
7.21.3.5 start_
```

The documentation for this class was generated from the following file:

std::string qpp::internal::IOManipPointer< PointerType >::start_ [private]


• internal/classes/iomanip.h

template<typename PointerType>


7.22 qpp::internal::IOManipRange < InputIterator > Class Template Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipRange< InputIterator >:



Collaboration diagram for qpp::internal::IOManipRange< InputIterator >:



Public Member Functions

- IOManipRange (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")
- IOManipRange (const IOManipRange &)=default
- IOManipRange & operator= (const IOManipRange &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- InputIterator first_
- InputIterator last
- std::string separator
- std::string start_
- · std::string end_

7.22.1 Constructor & Destructor Documentation

```
7.22.1.1 IOManipRange() [1/2]
```

7.22.1.2 IOManipRange() [2/2]

7.22.2 Member Function Documentation

7.22.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.22.2.2 operator=()

7.22.3 Member Data Documentation

```
7.22.3.1 end
```

```
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::end_ [private]
```

7.22.3.2 first_

```
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::first_ [private]
```

7.22.3.3 last_

```
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::last_ [private]
```

7.22.3.4 separator_

```
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::separator_ [private]
```

7.22.3.5 start_

```
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::start_ [private]
```

The documentation for this class was generated from the following file:


internal/classes/iomanip.h

7.23 qpp::IQCircuit Class Reference


Quantum circuit simulator abstract class.

#include <classes/circuits.h>

Inheritance diagram for qpp::IQCircuit:



Collaboration diagram for qpp::IQCircuit:



Public Member Functions

• IQCircuit (const QCircuitDescription &qcd)

Constructs a quantum circuit out of a quantum circuit description.

• IQCircuit (QCircuitDescription &&)=delete

Disables rvalue QCircuitDescription.

virtual ∼IQCircuit ()=default

Default virtual destructor.

• ket get_psi () const

Underlying quantum state.

ket & get_ref_psi ()

Reference to the underlying quantum state.

std::vector< idx > get_dits () const

Vector with the values of the underlying classical dits.

• idx get_dit (idx i) const

Value of the classical dit at position i.

std::vector< double > get_probs () const

Vector of underlying measurement outcome probabilities.

· idx get measured (idx i) const

Check whether qudit i was already measured.

• std::vector< idx > get_measured () const

Vector of already measured gudit indexes.

std::vector< idx > get_not_measured () const

Vector of non-measured qudit indexes.

bool is_measurement_step () const

Checks whether the current step in the circuit is a measurement step.

idx get_m_ip () const

Measurement instruction pointer.

idx get_q_ip () const

Quantum instruction pointer.

idx get_ip () const

Total instruction pointer.

· QCircuitDescription::const_iterator get_iter () const

Iterator to current step.

const QCircuitDescription & get_circuit_description () const

Quantum circuit description.

IQCircuit & set_dit (idx i, idx value)

Sets the classical dit at position i.

• void reset ()

Resets the quantum circuit.

• std::ostream & display (std::ostream &os) const override

qpp::IDisplay::display() override

• virtual void run (bool verbose=false, idx step=idx_infty)=0

Executes the quantum circuit, pure virtual member function that must be overridden by all derived classes.

Protected Member Functions

void set measured (idx i)

Marks qudit i as measured then re-label accordingly the remaining non-measured qudits.

std::vector< idx > get_relative_pos_ (std::vector< idx > v)

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

Protected Attributes

const QCircuitDescription & qcd

quantum circuit description

ket psi_

state vector

std::vector< idx > dits_

classical dits

```
    std::vector< double > probs_
        measurement probabilities
    std::vector< idx > subsys_
        relabel them after measurements
    QCircuitDescription::const_iterator it_
```

7.23.1 Detailed Description

Quantum circuit simulator abstract class.

iterator to current step

See also

```
qpp::QCircuitDescription
```

Note

Every further derived class has to override the run() member function

7.23.2 Constructor & Destructor Documentation

Constructs a quantum circuit out of a quantum circuit description.

Note

The quantum circuit description must be an Ivalue

See also

```
qpp::QCircuit(QCircuitDescription&&)
```

Note

The initial underlying quantum state is set to $|0\rangle^{\otimes n}$

Parameters

qcd	Quantum circuit description
-----	-----------------------------

Disables rvalue QCircuitDescription.

```
7.23.2.3 \simIQCircuit()
```

```
virtual qpp::IQCircuit::~IQCircuit ( ) [virtual], [default]
```

Default virtual destructor.

7.23.3 Member Function Documentation

7.23.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the quantum circuit

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.23.3.2 get_circuit_description()

```
const QCircuitDescription@ qpp::IQCircuit::get_circuit_description ( ) const [inline]
```

Quantum circuit description.

Returns

Quantum circuit description

7.23.3.3 get_dit()

```
idx qpp::IQCircuit::get_dit (
        idx i) const [inline]
```

Value of the classical dit at position i.

Parameters

```
i Classical dit index
```

Returns

Value of the classical dit at position i

7.23.3.4 get_dits()

```
std::vector<idx> qpp::IQCircuit::get_dits ( ) const [inline]
```

Vector with the values of the underlying classical dits.

Returns

Vector of underlying classical dits

7.23.3.5 get_ip()

```
idx qpp::IQCircuit::get_ip ( ) const [inline]
```

Total instruction pointer.

Returns

The sum of measurement instruction pointer and quantum instruction pointer

```
7.23.3.6 get_iter()
```

```
QCircuitDescription::const_iterator qpp::IQCircuit::get_iter ( ) const [inline]
```

Iterator to current step.

Returns

Iterator to current step in the circuit

```
7.23.3.7 get_m_ip()
```

```
idx qpp::IQCircuit::get_m_ip ( ) const [inline]
```

Measurement instruction pointer.

Points to the index of the next measurement to be executed from the std::vector<MeasureStep> of measurements in the circuit description

Returns

Measurement instruction pointer

7.23.3.8 get_measured() [1/2]

Check whether qudit *i* was already measured.

Parameters

```
i Qudit index
```

Returns

True if qudit *i* was already measured, false othwewise

```
7.23.3.9 get_measured() [2/2]
```

```
std::vector<idx> qpp::IQCircuit::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

7.23.3.10 get_not_measured()

```
std::vector<idx> qpp::IQCircuit::get_not_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

Returns

Vector of non-measured qudit indexes

7.23.3.11 get_probs()

```
std::vector<double> qpp::IQCircuit::get_probs ( ) const [inline]
```

Vector of underlying measurement outcome probabilities.

Note

The probability vector has the same length as the vector of classical dits. If the measurement result is stored at the index c_reg , then the outcome probability is automatically stored at the same index c_reg in the probability vector.

Returns

Vector of underlying measurement outcome probabilities

7.23.3.12 get_psi()

```
ket qpp::IQCircuit::get_psi ( ) const [inline]
```

Underlying quantum state.

Returns

Underlying quantum state

```
7.23.3.13 get_q_ip()
```

```
idx qpp::IQCircuit::get_q_ip ( ) const [inline]
```

Quantum instruction pointer.

Points to the index of the next quantum gate to be executed from the std::vector<GateStep> of quantum gates in the circuit description

Returns

Quantum instruction pointer

7.23.3.14 get_ref_psi()

```
ket& qpp::IQCircuit::get_ref_psi ( ) [inline]
```

Reference to the underlying quantum state.


Returns

Reference to the underlying quantum state

7.23.3.15 get_relative_pos_()

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

Parameters



7.23.3.16 is_measurement_step()

```
bool qpp::IQCircuit::is_measurement_step ( ) const [inline]
```

Checks whether the current step in the circuit is a measurement step.

Returns

True if measurement step, false otherwise

7.23.3.17 reset()

```
void qpp::IQCircuit::reset ( ) [inline]
```

Resets the quantum circuit.

Re-initializes everything to zero and sets the initial state to $|0\rangle^{\otimes n}$

7.23.3.18 run()

Executes the quantum circuit, pure virtual member function that must be overridden by all derived classes.

Parameters

verbose	If true, displays at console every executed step	
step	How many steps to execute, by default executes until the end	

Implemented in qpp::QCircuit.

7.23.3.19 set_dit()

Sets the classical dit at position i.

Parameters

i	Classical dit index
value	Classical dit value

Returns

Reference to the current instance

7.23.3.20 set_measured_()

Marks qudit *i* as measured then re-label accordingly the remaining non-measured qudits.

```
Parameters
```

```
i Qudit index
```

7.23.4 Member Data Documentation

```
7.23.4.1 dits_
std::vector<idx> qpp::IQCircuit::dits_ [protected]
classical dits
7.23.4.2 it_
QCircuitDescription::const_iterator qpp::IQCircuit::it_ [protected]
iterator to current step
7.23.4.3 probs_
std::vector<double> qpp::IQCircuit::probs_ [protected]
measurement probabilities
7.23.4.4 psi_
ket qpp::IQCircuit::psi_ [protected]
state vector
7.23.4.5 qcd_
const QCircuitDescription& qpp::IQCircuit::qcd_ [protected]
quantum circuit description
```

7.23.4.6 subsys_

```
std::vector<idx> qpp::IQCircuit::subsys_ [protected]
```

relabel them after measurements

keeps track of the measured subsystems,

The documentation for this class was generated from the following file:


· classes/circuits.h

7.24 qpp::is_complex< T > Struct Template Reference


Checks whether the type is a complex type.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_complex< T >:



Collaboration diagram for qpp::is_complex < T >:



7.24.1 Detailed Description

```
template < typename T> struct qpp::is_complex < T >
```

Checks whether the type is a complex type.

Provides the constant member value which is equal to true, if the type is a complex type, i.e. std::complex<T>

The documentation for this struct was generated from the following file:


· traits.h

7.25 qpp::is_complex < std::complex < T > > Struct Template Reference


Checks whether the type is a complex number type, specialization for complex types.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_complex< std::complex< T >>:



 $\label{local_complex} \mbox{Collaboration diagram for qpp::is_complex} < \mbox{std::complex} < \mbox{T} >>:$



7.25.1 Detailed Description

```
\label{template} \begin{tabular}{ll} template < typename T > \\ struct qpp::is\_complex < std::complex < T > > \\ \end{tabular}
```

Checks whether the type is a complex number type, specialization for complex types.

The documentation for this struct was generated from the following file:


· traits.h

7.26 qpp::is_iterable < T, typename > Struct Template Reference


Checks whether *T* is compatible with an STL-like iterable container.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_iterable < T, typename >:



Collaboration diagram for qpp::is_iterable < T, typename >:



7.26.1 Detailed Description

```
template<typename T, typename = void>
struct qpp::is_iterable< T, typename >
```

Checks whether T is compatible with an STL-like iterable container.

Provides the constant member *value* which is equal to *true*, if *T* is compatible with an iterable container, i.e. provides at least *begin()* and *end()* member functions and allows de-referencing. Otherwise, *value* is equal to *false*.

The documentation for this struct was generated from the following file:


· traits.h

7.27 qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().begin())) > Struct Template Reference


Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

```
#include <traits.h>
```

 $Inheritance\ diagram\ for\ qpp::is_iterable<\ T,\ to_void<\ decltype(std::declval<\ T>().begin()),\ decltype(std::declval<\ T>().begin()))>>:$



Collaboration diagram for qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().begin())) > :



7.27.1 Detailed Description

 $template < typename \ T > \\ struct \ qpp::is_iterable < T, \ to_void < decltype(std::declval < T > ().begin()), \ decltype(std::declval < T > ().end()), \ decltype(*(std \leftarrow ::declval < T > ().begin())) > \\ \end{cases}$

Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

The documentation for this struct was generated from the following file:


• traits.h

7.28 qpp::is_matrix_expression < Derived > Struct Template Reference


Checks whether the type is an Eigen matrix expression.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_matrix_expression< Derived >:



Collaboration diagram for qpp::is_matrix_expression< Derived >:



7.28.1 Detailed Description

```
template < typename Derived > struct qpp::is_matrix_expression < Derived >
```

Checks whether the type is an Eigen matrix expression.

Provides the constant member *value* which is equal to *true*, if the type is an Eigen matrix expression of type *Eigen ∷MatrixBase Oerived .* Otherwise, *value* is equal to *false*.

The documentation for this struct was generated from the following file:


· traits.h

7.29 qpp::QCircuitDescription::iterator Class Reference

Quantum circuit description bound-checking (safe) iterator.

```
#include <classes/circuits.h>
```

Collaboration diagram for qpp::QCircuitDescription::iterator:



Classes

struct value_type_

Public Types

• using difference_type = long long

iterator trait

using value_type = value_type_

iterator trait

using pointer = const value_type *

iterator trait

• using reference = const value_type &

iterator trait

• using iterator_category = std::forward_iterator_tag

iterator trait

Public Member Functions

• iterator ()=default

Default constructor.

• iterator (const iterator &)=default

Default copy constructor.

iterator & operator= (const iterator &)=default

Default copy assignment operator.

iterator & operator++ ()

Prefix increment operator.

iterator operator++ (int)

Postfix increment operator.

• bool operator== (const iterator &rhs) const

Equality operator.

• bool operator!= (iterator rhs) const

Inequality operator.

• const value_type_ & operator* () const

Safe de-referencing operator.

Private Member Functions

• void set_ (const QCircuitDescription *qcd)

Sets the internal quantum circuit description pointer.

Private Attributes

- friend QCircuitDescription
- const QCircuitDescription * qcd_ {nullptr}

iterator value type

value_type_ elem_ {nullptr}

de-referenced iterator element

Friends

· class IQCircuit

non-owning pointer to const circuit description

7.29.1 Detailed Description

Quantum circuit description bound-checking (safe) iterator.

Note

The iterator is a const_iterator by default

7.29.2 Member Typedef Documentation

7.29.2.1 difference_type

```
using qpp::QCircuitDescription::iterator::difference_type = long long
```

iterator trait

7.29.2.2 iterator_category

```
using qpp::QCircuitDescription::iterator::iterator_category = std::forward_iterator_tag
```

iterator trait

7.29.2.3 pointer

```
using qpp::QCircuitDescription::iterator::pointer = const value_type*
```

iterator trait

7.29.2.4 reference

```
using qpp::QCircuitDescription::iterator::reference = const value_type&
```

iterator trait

7.29.2.5 value_type

```
using qpp::QCircuitDescription::iterator::value_type = value_type_
```

iterator trait

7.29.3 Constructor & Destructor Documentation

```
7.29.3.1 iterator() [1/2]

qpp::QCircuitDescription::iterator::iterator ( ) [default]

Default constructor.

7.29.3.2 iterator() [2/2]

qpp::QCircuitDescription::iterator::iterator (
```

const iterator &) [default]

Default copy constructor.

7.29.4 Member Function Documentation

7.29.4.1 operator"!=()

Inequality operator.

Parameters

rhs Iterator against which the inequality is being tested

Returns

True if the iterators are not equal (bit by bit), false otherwise

```
7.29.4.2 operator*()
```

```
const value_type_& qpp::QCircuitDescription::iterator::operator* ( ) const [inline]
```

Safe de-referencing operator.

Returns

Constant reference to the iterator element

```
7.29.4.3 operator++() [1/2]
```

```
iterator& qpp::QCircuitDescription::iterator::operator++ ( ) [inline]
```

Prefix increment operator.

Returns

Reference to the current instance

```
7.29.4.4 operator++() [2/2]
```

Postfix increment operator.

Returns

Copy of the current instance before the increment

7.29.4.5 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

7.29.4.6 operator==()

Equality operator.

Parameters

rhs | Iterator against which the equality is being tested

Returns

True if the iterators are equal, false otherwise

Sets the internal quantum circuit description pointer.

Parameters

qcd Constant pointer to a quantum circuit description

7.29.5 Friends And Related Function Documentation

```
7.29.5.1 IQCircuit
```

```
friend class IQCircuit [friend]
```

non-owning pointer to const circuit description

7.29.6 Member Data Documentation

```
7.29.6.1 elem_
```

```
value_type_ qpp::QCircuitDescription::iterator::elem_ {nullptr} [private]
```

de-referenced iterator element

```
7.29.6.2 qcd_
```

```
const QCircuitDescription* qpp::QCircuitDescription::iterator::qcd_ {nullptr} [private]
```

iterator value type

7.29.6.3 QCircuitDescription

```
friend qpp::QCircuitDescription::iterator::QCircuitDescription [private]
```

The documentation for this class was generated from the following file:

· classes/circuits.h

7.30 qpp::make_void < Ts > Struct Template Reference

Helper for qpp::to_void<>> alias template.

```
#include <traits.h>
```

Public Types

· typedef void type

7.30.1 Detailed Description

```
template<typename... Ts>
struct qpp::make_void< Ts>
```

Helper for qpp::to_void<>> alias template.

See also

qpp::to_void<>

7.30.2 Member Typedef Documentation

```
7.30.2.1 type
```

```
template<typename... Ts>
typedef void qpp::make_void< Ts >::type
```

The documentation for this struct was generated from the following file:


· traits.h

7.31 qpp::exception::MatrixMismatchSubsys Class Reference


Matrix mismatch subsystems exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixMismatchSubsys:



Collaboration diagram for qpp::exception::MatrixMismatchSubsys:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.31.1 Detailed Description

Matrix mismatch subsystems exception.

Matrix size mismatch subsystem sizes (e.g. in qpp::apply())

7.31.2 Member Function Documentation

7.31.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.31.2.2 type_description()

std::string qpp::exception::MatrixMismatchSubsys::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.32 qpp::exception::MatrixNotCvector Class Reference


Matrix is not a column vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotCvector:



Collaboration diagram for qpp::exception::MatrixNotCvector:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.32.1 Detailed Description

Matrix is not a column vector exception.

Eigen::Matrix is not a column vector

7.32.2 Member Function Documentation

7.32.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.32.2.2 type_description()

std::string qpp::exception::MatrixNotCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.33 qpp::exception::MatrixNotRvector Class Reference


Matrix is not a row vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotRvector:



Collaboration diagram for qpp::exception::MatrixNotRvector:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.33.1 Detailed Description

Matrix is not a row vector exception.

Eigen::Matrix is not a row vector

7.33.2 Member Function Documentation

7.33.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.33.2.2 type_description()

std::string qpp::exception::MatrixNotRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.34 qpp::exception::MatrixNotSquare Class Reference


Matrix is not square exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquare:



Collaboration diagram for qpp::exception::MatrixNotSquare:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.34.1 Detailed Description

Matrix is not square exception.

Eigen::Matrix is not a square matrix

7.34.2 Member Function Documentation

7.34.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.34.2.2 type_description()

std::string qpp::exception::MatrixNotSquare::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.35 qpp::exception::MatrixNotSquareNorCvector Class Reference


Matrix is not square nor column vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorCvector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorCvector:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.35.1 Detailed Description

Matrix is not square nor column vector exception.

Eigen::Matrix is not a square matrix nor a column vector

7.35.2 Member Function Documentation

7.35.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.35.2.2 type_description()

```
std::string qpp::exception::MatrixNotSquareNorCvector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.36 qpp::exception::MatrixNotSquareNorRvector Class Reference


Matrix is not square nor row vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorRvector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorRvector:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.36.1 Detailed Description

Matrix is not square nor row vector exception.

Eigen::Matrix is not a square matrix nor a row vector

7.36.2 Member Function Documentation

7.36.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

```
where Text representing where the exception occurred
```

7.36.2.2 type_description()

```
std::string qpp::exception::MatrixNotSquareNorRvector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.37 qpp::exception::MatrixNotSquareNorVector Class Reference


Matrix is not square nor vector exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Square Nor Vector:$



Collaboration diagram for qpp::exception::MatrixNotSquareNorVector:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.37.1 Detailed Description

Matrix is not square nor vector exception.

Eigen::Matrix is not a square matrix nor a row/column vector

7.37.2 Member Function Documentation

7.37.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.37.2.2 type_description()

```
std::string qpp::exception::MatrixNotSquareNorVector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.38 qpp::exception::MatrixNotVector Class Reference


Matrix is not a vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotVector:



Collaboration diagram for qpp::exception::MatrixNotVector:



• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.38.1 Detailed Description

Matrix is not a vector exception.

Eigen::Matrix is not a row or column vector

7.38.2 Member Function Documentation

7.38.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.38.2.2 type_description()

std::string qpp::exception::MatrixNotVector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description


Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

7.39 qpp::QCircuitDescription::MeasureStep Struct Reference

One step consisting only of measurements in the circuit.

Collaboration diagram for qpp::QCircuitDescription::MeasureStep:



Public Member Functions

• MeasureStep ()=default

Default constructor.

MeasureStep (MeasureType measurement_type, const std::vector < cmat > &mats, const std::vector < idx > &target, idx c_reg, idx step_no, std::string name="")

Constructs a measurement step instance.

Public Attributes

• MeasureType measurement_type_ = MeasureType::NONE

measurement type

- std::vector< cmat > mats_
- std::vector < idx > target_

measurement

idx c_reg_ {}

result is being stored

· idx step_no_

step number

• std::string name_

custom name of the step

7.39.1 Detailed Description

One step consisting only of measurements in the circuit.

7.39.2 Constructor & Destructor Documentation

```
7.39.2.1 MeasureStep() [1/2]

qpp::QCircuitDescription::MeasureStep::MeasureStep ( ) [default]
```

7.39.2.2 MeasureStep() [2/2]

Default constructor.

Constructs a measurement step instance.

Parameters

measurement_type	Measurement type
mats	Vector of measurement matrices (can be only one or many for Kraus measurements)
target	Target qudit indexes
c_reg	Classical register where the value of the measurement is stored
step_no	Circuit step number
name	Optional gate name

7.39.3 Member Data Documentation

```
7.39.3.1 c_reg_
idx qpp::QCircuitDescription::MeasureStep::c_reg_ {}
```

index of the classical register where the measurement

result is being stored

```
7.39.3.2 mats_
std::vector<cmat> qpp::QCircuitDescription::MeasureStep::mats_
matrix/matrices that specify the
7.39.3.3 measurement_type_
MeasureType qpp::QCircuitDescription::MeasureStep::measurement_type_ = MeasureType::NONE
measurement type
7.39.3.4 name_
std::string qpp::QCircuitDescription::MeasureStep::name_
custom name of the step
7.39.3.5 step_no_
idx qpp::QCircuitDescription::MeasureStep::step_no_
step number
7.39.3.6 target_
std::vector<idx> qpp::QCircuitDescription::MeasureStep::target_
measurement
target where the measurement is applied
The documentation for this struct was generated from the following file:
```


· classes/circuits.h

7.40 qpp::exception::NoCodeword Class Reference


Codeword does not exist exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NoCodeword:



Collaboration diagram for qpp::exception::NoCodeword:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.40.1 Detailed Description

Codeword does not exist exception.

Codeword does not exist, thrown when calling qpp::Codes::codeword() with an invalid index

7.40.2 Member Function Documentation

7.40.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.40.2.2 type_description()

```
std::string qpp::exception::NoCodeword::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.41 qpp::NoiseBase < T > Class Template Reference

Base class for all noise models, derive your particular noise model.

#include <classes/noise.h>

Collaboration diagram for qpp::NoiseBase< T >:



Public Types

• using noise_type = T

Public Member Functions

template<typename U = noise_type>
 NoiseBase (const std::vector< cmat > &Ks, typename std::enable_if< std::is_same< NoiseType::StateDependent,
 U >::value >::type *=nullptr)

Constructs a noise instance for StateDependent noise type.

• template<typename U = noise_type>

 $\label{local_NoiseBase} NoiseBase \ (const \ std::vector < cmat > \&Ks, \ const \ std::vector < double > \&probs, \ typename \ std::enable_if < std::is_same < NoiseType::StateIndependent, \ U >::value >::type *=nullptr)$

Constructs a noise instance for StateIndependent noise type.

virtual ∼NoiseBase ()=default

Default virtual destructor.

idx get_d () const

Local dimension.

std::vector< cmat > get_Ks () const

Vector of noise operators.

• std::vector< double > get_probs () const

Vector of probabilities corresponding to each noise operator.

• idx get_last_idx () const

Index of the last occurring noise element.

double get_last_p () const

Probability of the last occurring noise element.

cmat get_last_K () const

Last occurring noise element.

· virtual cmat operator() (const cmat &state, idx target) const

Function invocation operator, applies the underlying noise model on qudit target of the multi-partite state vector or density matrix state.

• virtual cmat operator() (const cmat &state, const std::vector< idx > &target) const

Function invocation operator, applies the underlying correlated noise model on qudits specified by target of the multipartite state vector or density matrix state.

Protected Member Functions

- void compute_probs_ (const cmat &state, const std::vector < idx > &target) const
 Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)
- cmat compute_state_ (const cmat &state, const std::vector< idx > &target) const Compute the resulting state after the noise was applied.

Protected Attributes

```
• const std::vector< cmat > Ks_
```

Kraus operators.

• std::vector< double > probs_

probabilities

• idx d_{}

qudit dimension

idx i_{}

index of the last occurring noise element

bool generated_ {false}

invoked, or if the noise is state-independent

7.41.1 Detailed Description

```
template < class T > class qpp::NoiseBase < T >
```

Base class for all noise models, derive your particular noise model.

7.41.2 Member Typedef Documentation

7.41.2.1 noise_type

```
template<class T>
using qpp::NoiseBase< T >::noise_type = T
```

7.41.3 Constructor & Destructor Documentation

7.41.3.1 NoiseBase() [1/2]

Constructs a noise instance for StateDependent noise type.

Note

SFINAEd-out for StateIndependent noise

Parameters

Α	Eigen expression (state vector or density matrix)	
Ks	Vector of noise (Kraus) operators that specify the noise	
d	Subsystem dimension	

7.41.3.2 NoiseBase() [2/2]

Constructs a noise instance for StateIndependent noise type.

Note

SFINAEd-out for StateDependent noise

Parameters

Α	Eigen expression (state vector or density matrix)
Ks	Vector of noise (Kraus) operators that specify the noise
d	Subsystem dimension

7.41.3.3 ∼NoiseBase()

```
template<class T>
virtual qpp::NoiseBase< T >::~NoiseBase () [virtual], [default]
```

Default virtual destructor.

7.41.4 Member Function Documentation

7.41.4.1 compute_probs_()

Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

Parameters

state	State vector or density matrix
target	Qudit indexes where the noise is applied

7.41.4.2 compute_state_()

Compute the resulting state after the noise was applied.

Parameters

state	State vector or density matrix
target	Qudit indexes where the noise is applied

Returns

Resulting state after the noise was applied

```
7.41.4.3 get_d()
```

```
template<class T>
idx qpp::NoiseBase< T >::get_d ( ) const [inline]
```

Local dimension.

Returns

Local dimension

7.41.4.4 get_Ks()

```
template<class T>
std::vector<cmat> qpp::NoiseBase< T >::get_Ks ( ) const [inline]
```

Vector of noise operators.

Returns

Vector of noise operators

7.41.4.5 get_last_idx()

```
template<class T>
idx qpp::NoiseBase< T >::get_last_idx ( ) const [inline]
```

Index of the last occurring noise element.

Returns

Index of the last occurring noise element

7.41.4.6 get_last_K()

```
template<class T>
cmat qpp::NoiseBase< T >::get_last_K ( ) const [inline]
```

Last occurring noise element.

Returns

Last occurring noise element

7.41.4.7 get_last_p()

```
template<class T>
double qpp::NoiseBase< T >::get_last_p ( ) const [inline]
```

Probability of the last occurring noise element.

Returns

Probability of the last occurring noise element

7.41.4.8 get_probs()

```
template<class T>
std::vector<double> qpp::NoiseBase< T >::get_probs ( ) const [inline]
```

Vector of probabilities corresponding to each noise operator.

Returns

Probability vector

7.41.4.9 operator()() [1/2]

Function invocation operator, applies the underlying noise model on qudit *target* of the multi-partite state vector or density matrix *state*.

Parameters

state	Multi-partite state vector or density matrix
target	Qudit index where the noise is applied

Returns

Resulting state vector or density matrix

7.41.4.10 operator()() [2/2]

Function invocation operator, applies the underlying correlated noise model on qudits specified by *target* of the multi-partite state vector or density matrix *state*.

Parameters

state	Multi-partite state vector or density matrix
target	Qudit indexes where the correlated noise is applied

Returns

Resulting state vector or density matrix

7.41.5 Member Data Documentation

```
7.41.5.1 d
```

```
template<class T>
idx qpp::NoiseBase< T >::d_ {} [mutable], [protected]
```

7.41.5.2 generated_

qudit dimension

```
template<class T>
bool qpp::NoiseBase< T >::generated_ {false} [mutable], [protected]
```

invoked, or if the noise is state-independent

set to true after compute_state_() is

7.41.5.3 i_

```
template<class T>
idx qpp::NoiseBase< T >::i_ {} [mutable], [protected]
```

index of the last occurring noise element

7.41.5.4 Ks_

```
template<class T>
const std::vector<cmat> qpp::NoiseBase< T >::Ks_ [protected]
```

Kraus operators.

7.41.5.5 probs_

```
template<class T>
std::vector<double> qpp::NoiseBase< T >::probs_ [mutable], [protected]
```

probabilities

The documentation for this class was generated from the following file:

· classes/noise.h

7.42 qpp::NoiseType Class Reference

Contains template tags used to specify the noise type.

```
#include <classes/noise.h>
```

Classes

· class StateDependent

Template tag, used whenever the noise is state-dependent.

• class StateIndependent

Template tag, used whenever the noise is state-independent.

7.42.1 Detailed Description

Contains template tags used to specify the noise type.

The documentation for this class was generated from the following file:


• classes/noise.h

7.43 qpp::exception::NotBipartite Class Reference


Not bi-partite exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotBipartite:



Collaboration diagram for qpp::exception::NotBipartite:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.43.1 Detailed Description

Not bi-partite exception.

std::vector<idx> of dimensions has size different from 2

7.43.2 Member Function Documentation

7.43.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.43.2.2 type_description()

```
std::string qpp::exception::NotBipartite::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.44 qpp::exception::NotImplemented Class Reference


Code not yet implemented.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotImplemented:



Collaboration diagram for qpp::exception::NotImplemented:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.44.1 Detailed Description

Code not yet implemented.

7.44.2 Member Function Documentation

7.44.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.44.2.2 type_description()

```
std::string qpp::exception::NotImplemented::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.45 qpp::exception::NotQubitCvector Class Reference


Column vector is not 2 x 1 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitCvector:



Collaboration diagram for qpp::exception::NotQubitCvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.45.1 Detailed Description

Column vector is not 2 x 1 exception.

Eigen::Matrix is not 2 x 1

7.45.2 Member Function Documentation

7.45.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.45.2.2 type_description()

std::string qpp::exception::NotQubitCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.46 qpp::exception::NotQubitMatrix Class Reference


Matrix is not 2 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitMatrix:



Collaboration diagram for qpp::exception::NotQubitMatrix:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.46.1 Detailed Description

Matrix is not 2 x 2 exception.

Eigen::Matrix is not 2 x 2

7.46.2 Member Function Documentation

7.46.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.46.2.2 type_description()

```
std::string qpp::exception::NotQubitMatrix::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.47 qpp::exception::NotQubitRvector Class Reference


Row vector is not 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitRvector:



Collaboration diagram for qpp::exception::NotQubitRvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.47.1 Detailed Description

Row vector is not 1 x 2 exception.

Eigen::Matrix is not 1 x 2

7.47.2 Member Function Documentation

7.47.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.47.2.2 type_description()

std::string qpp::exception::NotQubitRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.48 qpp::exception::NotQubitSubsys Class Reference


Subsystems are not qubits exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitSubsys:



Collaboration diagram for qpp::exception::NotQubitSubsys:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.48.1 Detailed Description

Subsystems are not qubits exception.

Subsystems are not 2-dimensional (qubits)

7.48.2 Member Function Documentation

7.48.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

7.48.2.2 type_description()

```
std::string qpp::exception::NotQubitSubsys::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.49 qpp::exception::NotQubitVector Class Reference


Vector is not 2 x 1 nor 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitVector:



Collaboration diagram for qpp::exception::NotQubitVector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.49.1 Detailed Description

Vector is not 2 x 1 nor 1 x 2 exception.

Eigen::Matrix is not 2 x 1 nor 1 x 2

7.49.2 Member Function Documentation

7.49.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.49.2.2 type_description()

```
std::string qpp::exception::NotQubitVector::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.50 qpp::exception::OutOfRange Class Reference


Argument out of range exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::OutOfRange:



Collaboration diagram for qpp::exception::OutOfRange:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.50.1 Detailed Description

Argument out of range exception.

Argument out of range

7.50.2 Member Function Documentation

7.50.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.50.2.2 type_description()

```
std::string qpp::exception::OutOfRange::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.51 qpp::exception::PermInvalid Class Reference


Invalid permutation exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermInvalid:



Collaboration diagram for qpp::exception::PermInvalid:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.51.1 Detailed Description

Invalid permutation exception.

std::vector<idx> does note represent a valid permutation

7.51.2 Member Function Documentation

7.51.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.51.2.2 type_description()

```
std::string qpp::exception::PermInvalid::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.52 qpp::exception::PermMismatchDims Class Reference


Permutation mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermMismatchDims:



Collaboration diagram for qpp::exception::PermMismatchDims:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.52.1 Detailed Description

Permutation mismatch dimensions exception.

Size of the std::vector<idx> representing the permutation is different from the size of the std::vector<idx> of dimensions

7.52.2 Member Function Documentation

7.52.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
******	Toxt representing where the exception eccurred

7.52.2.2 type_description()

```
std::string qpp::exception::PermMismatchDims::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

7.53 qpp::QCircuit Class Reference


Quantum circuit simulator class.

#include <classes/circuits.h>

Inheritance diagram for qpp::QCircuit:



Collaboration diagram for qpp::QCircuit:



Public Member Functions

- void run (bool verbose=false, idx step=idx_infty) override
 - < Uses the base IQCircuit constructor
- IQCircuit (const QCircuitDescription &qcd)

Constructs a quantum circuit out of a quantum circuit description.

• IQCircuit (QCircuitDescription &&)=delete

Disables rvalue QCircuitDescription.

Additional Inherited Members

7.53.1 Detailed Description

Quantum circuit simulator class.

See also

qpp::QCircuitDescription

7.53.2 Member Function Documentation

```
7.53.2.1 IQCircuit() [1/2]
```

```
qpp::IQCircuit::IQCircuit [inline], [explicit]
```

Constructs a quantum circuit out of a quantum circuit description.

Note

The quantum circuit description must be an Ivalue

See also

qpp::QCircuit(QCircuitDescription&&)

Note

The initial underlying quantum state is set to $|0\rangle^{\otimes n}$

Parameters

qcd Quantum circuit description

```
7.53.2.2 IQCircuit() [2/2]
```

```
qpp::IQCircuit::IQCircuit [delete]
```

Disables rvalue QCircuitDescription.

7.53.2.3 run()

< Uses the base IQCircuit constructor

Executes the quantum circuit, qpp::IQCircuit::run() override

Parameters

verbose	If true, displays at console every executed step
step	How many steps to execute, by default executes until the end

Implements qpp::IQCircuit.

The documentation for this class was generated from the following file:


· classes/circuits.h

7.54 qpp::QCircuitDescription Class Reference


Quantum circuit description class.

```
#include <classes/circuits.h>
```

Inheritance diagram for qpp::QCircuitDescription:



Collaboration diagram for qpp::QCircuitDescription:



Classes

struct GateStep

One step consisting only of gates/operators in the circuit.

· class iterator

Quantum circuit description bound-checking (safe) iterator.

struct MeasureStep

One step consisting only of measurements in the circuit.

Public Types

enum GateType {

GateType::NONE, GateType::SINGLE, GateType::TWO, GateType::THREE,

GateType::CUSTOM, GateType::FAN, GateType::QFT, GateType::TFQ,

 ${\tt GateType::SINGLE_CTRL_SINGLE_TARGET, GateType::SINGLE_CTRL_MULTIPLE_TARGET, GateType::MULTIPLE_CTRL_MULTIPLE_TARGET, GateType::MULTIPLE_CTRL_MULTIPLE_TARGET, GateType::MULTIPLE_CTRL_MULTIPLE_TARGET, GateType::MULTIPLE_CTRL_MULTIPLE_TARGET, GateType::MULTIPLE_CTRL_MULTIPLE_TARGET, GateType::MULTIPLE_CTRL_$

GateType::MULTIPLE_CTRL_MULTIPLE_TARGET,

GateType::CUSTOM_CTRL, GateType::SINGLE_cCTRL_SINGLE_TARGET, GateType::SINGLE_cCTRL_MULTIPLE_TARGET

GateType::MULTIPLE_cCTRL_SINGLE_TARGET,

GateType::MULTIPLE_cCTRL_MULTIPLE_TARGET, GateType::CUSTOM_cCTRL }

Type of gate being executed in a gate step.

 enum MeasureType { MeasureType::NONE, MeasureType::MEASURE_Z, MeasureType::MEASURE_V, MeasureType::MEASURE_V_MANY }

Type of measurement being executed in a measurement step.

using const_iterator = iterator

both iterators are const_iterators

Public Member Functions

• iterator begin ()

Iterator to the first element.

const_iterator begin () const noexcept

Constant iterator to the first element.

• const_iterator cbegin () const noexcept

Constant iterator to the first element.

• iterator end ()

Iterator to the next to the last element.

· const_iterator end () const noexcept

Constant iterator to the next to the last element.

const_iterator cend () const noexcept

Constant iterator to the next to the last element.

• QCircuitDescription (idx nq, idx nc=0, idx d=2, std::string name="")

Constructs a quantum circuit description.

virtual ~QCircuitDescription ()=default

Default virtual destructor.

• idx get_nq () const noexcept

Total number of qudits in the circuit.

idx get_nc () const noexcept

Total number of classical dits in the circuit.

• idx get d () const noexcept

Local dimension of the comprising qudits.

std::vector< idx > get_measurement_steps () const

Vector of measurement positions in the circuit, i.e. the indexes where the measurements take place.

• const std::vector< MeasureStep > & get_measurements () const noexcept

Vector of qpp::QCircuitDescription::MeasureStep.

const std::vector< GateStep > & get_gates () const noexcept

Vector of qpp::QCircuitDescription::GateStep.

std::string get_name () const

Quantum circuit name.

idx get_measured (idx i) const

Check whether qudit i was already measured.

std::vector< idx > get measured () const

Vector of already measured qudit indexes.

std::vector< idx > get_non_measured () const

Vector of non-measured qudit indexes.

idx get_gate_count () const noexcept

Quantum circuit total gate count.

idx get_measurement_count () const noexcept

Quantum circuit total measurement count.

idx get_steps_count () const noexcept

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

QCircuitDescription & gate (const cmat &U, idx i, std::string name="")

Applies the single qudit gate U on single qudit i.

QCircuitDescription & gate (const cmat &U, idx i, idx j, std::string name="")

Applies the two qudit gate U on gudits i and j.

QCircuitDescription & gate (const cmat &U, idx i, idx j, idx k, std::string name="")

Applies the three qudit gate U on qudits i, j and k.

QCircuitDescription & gate fan (const cmat &U, const std::vector < idx > &target, std::string name="")

Applies the single qudit gate U on every qudit listed in target.

QCircuitDescription & gate_fan (const cmat &U, std::string name="")

Applies the single qudit gate U on every remaining non-measured qudit.

QCircuitDescription & gate_custom (const cmat &U, const std::vector < idx > &target, std::string name="")

Jointly applies the custom multiple qudit gate U on the qudit indexes specified by target.

QCircuitDescription & QFT (const std::vector < idx > &target, bool swap QPP_UNUSED_=true)

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuitDescription & TFQ (const std::vector< idx > &target, bool swap QPP_UNUSED_=true)

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuitDescription & CTRL (const cmat &U, idx ctrl, idx target, std::string name="")

Applies the single qudit controlled gate U with control qudit ctrl and target qudit target.

QCircuitDescription & CTRL (const cmat &U, idx ctrl, const std::vector < idx > &target, std::string name="")

Applies the single qudit controlled gate U with control qudit ctrl on every qudit listed in target.

QCircuitDescription & CTRL (const cmat &U, const std::vector < idx > &ctrl, idx target, std::string name="")

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on the target qudit target.

QCircuitDescription & CTRL (const cmat &U, const std::vector< idx > &ctrl, const std::vector< idx > &target, std::string name="")

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on every qudit listed in target.

QCircuitDescription & CTRL_custom (const cmat &U, const std::vector< idx > &ctrl, const std::vector< idx > &target, std::string name="")

Jointly applies the custom multiple-qudit controlled gate U with multiple control qudits listed in ctrl on the qudit indexes specified by target.

QCircuitDescription & cCTRL (const cmat &U, idx ctrl dit, idx target, std::string name="")

Applies the single qubit controlled gate U with classical control dit ctrl and target qudit target.

 QCircuitDescription & cCTRL (const cmat &U, idx ctrl_dit, const std::vector< idx > &target, std::string name="")

Applies the single qudit controlled gate U with classical control dit ctrl on every qudit listed in target.

QCircuitDescription & cCTRL (const cmat &U, const std::vector< idx > &ctrl dits, idx target, std::string

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on the target qudit target.

 QCircuitDescription & cCTRL (const cmat &U, const std::vector< idx > &ctrl_dits, const std::vector< idx > &target, std::string name="")

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on every qudit listed in target.

 QCircuitDescription & cCTRL custom (const cmat &U, const std::vector < idx > &ctrl dits, const std::vector < idx > &target, std::string name="")

Jointly applies the custom multiple-qudit controlled gate U with multiple classical control dits listed in ctrl on the qudit indexes specified by target.

QCircuitDescription & measureZ (idx i, idx c reg, std::string name="")

Measurement of single qudit in the computational basis (Z-basis)

• QCircuitDescription & measureV (const cmat &V, idx i, idx c_reg, std::string name="")

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

 QCircuitDescription & measureV (const cmat &V, const std::vector< idx > &target, idx c_reg, std::string name="")

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix

• std::ostream & display (std::ostream &os) const override

```
gpp::IDisplay::display() override
```

std::string to_JSON () const

Protected Member Functions

• std::string to JSON () const

Private Attributes

const idx nq

```
number of qudits

    const idx nc

     number of classical "dits"

    const idx d

      qudit dimension
std::vector< idx > measurement_steps_ {}
```

measurements take place

· std::string name_

optional circuit name

std::vector< bool > measured

keeps track of the measured qudits

idx steps cnt

step counter

std::vector< GateStep > gates_{}{}

std::vector< MeasureStep > measurements {}

measurements

Friends

- std::ostream & operator << (std::ostream &os, const GateType &gate_type)
 Extraction operator overload for gpp::QCircuitDescription::GateType enum class.
- std::ostream & operator << (std::ostream &os, const MeasureType &measure_type)

 Extraction operator overload for qpp::QCircuitDescription::MeasureType enum class.
- std::ostream & operator << (std::ostream &os, const GateStep &gate_step)

 Extraction operator overload for qpp::QCircuitDescription::GateStep class.
- std::ostream & operator<< (std::ostream &os, const MeasureStep &measure_step)

 Extraction operator overload for qpp::QCircuitDescription::MeasureStep class.

7.54.1 Detailed Description

Quantum circuit description class.

See also

qpp::QCircuit

7.54.2 Member Typedef Documentation

7.54.2.1 const_iterator

using qpp::QCircuitDescription::const_iterator = iterator

both iterators are const_iterators

7.54.3 Member Enumeration Documentation

7.54.3.1 GateType

enum qpp::QCircuitDescription::GateType [strong]

Type of gate being executed in a gate step.

Enumerator

NONE	represents no gate
SINGLE	unitary gate on a single qudit
TWO	unitary gate on 2 qudits
THREE	unitary gate on 3 qudits
CUSTOM	custom gate on multiple qudits
FAN	same unitary gate on multiple qudits

Generated by Doxygen

Enumerator

QFT	quantum Fourier transform,
TFQ	quantum inverse Fourier transform,
SINGLE_CTRL_SINGLE_TARGET	one control and one target controlled 1 qudit unitary gate with
SINGLE_CTRL_MULTIPLE_TARGET	one control and multiple targets controlled 1 qudit unitary gate with
MULTIPLE_CTRL_SINGLE_TARGET	multiple controls and single target controlled 1 qudit unitary gate with
MULTIPLE_CTRL_MULTIPLE_TARGET	multiple controls and multiple targets controlled 1 qudit unitary gate with
CUSTOM_CTRL	and multiple targets custom controlled gate with multiple controls
SINGLE_cCTRL_SINGLE_TARGET	one classical control and one target controlled 1 qudit unitary gate with
SINGLE_cCTRL_MULTIPLE_TARGET	one classical control and multiple targets controlled 1 qudit unitary gate with
MULTIPLE_cCTRL_SINGLE_TARGET	multiple classical controls and single target controlled 1 qudit unitary gate with
MULTIPLE_cCTRL_MULTIPLE_TARGET	with multiple classical controls and multiple targets controlled 1 qudit unitary gate
CUSTOM_cCTRL	multiple targets custom controlled gate with multiple controls and

7.54.3.2 MeasureType

```
enum qpp::QCircuitDescription::MeasureType [strong]
```

Type of measurement being executed in a measurement step.

Enumerator

NONE	represents no measurement
MEASURE_Z Z measurement of single qudit.	
MEASURE_V or rank-1 projectors specified by the columns of matrix V measurement of single in the orthonormal basis	
MEASURE_V_MANY	basis or rank-1 projectors specified by the columns of matrix <i>V</i> measurement of multiple qudits in the orthonormal

7.54.4 Constructor & Destructor Documentation

7.54.4.1 QCircuitDescription()

```
idx nc = 0,
idx d = 2,
std::string name = "") [inline], [explicit]
```

Constructs a quantum circuit description.

Note

The measurement results can only be stored in the classical dits of which number is specified by *nc*

Parameters

nq	Number of qbits	
nc	Number of classical dits	
d	d Subsystem dimensions (optional, default is qubit, i.e. $d = 2$	
name	Circuit description name (optional)	

7.54.4.2 ~QCircuitDescription()

```
\label{local_continuit} \mbox{virtual qpp::QCircuitDescription::$\sim$QCircuitDescription ( ) [virtual], [default] \\
```

Default virtual destructor.

7.54.5 Member Function Documentation

```
7.54.5.1 _to_JSON()
```

```
std::string qpp::QCircuitDescription::_to_JSON ( ) const [inline], [protected]
```

```
7.54.5.2 begin() [1/2]
```

```
iterator qpp::QCircuitDescription::begin ( ) [inline]
```

Iterator to the first element.

Returns

Iterator to the first element

```
7.54.5.3 begin() [2/2]
```

```
const_iterator qpp::QCircuitDescription::begin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

7.54.5.4 cbegin()

```
const_iterator qpp::QCircuitDescription::cbegin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

```
7.54.5.5 cCTRL() [1/4]
```

Applies the single qubit controlled gate *U* with classical control dit *ctrl* and target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.6 cCTRL() [2/4]
```

Applies the single qudit controlled gate *U* with classical control dit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the
	classical control dits
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.7 cCTRL() [3/4]
```

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.8 cCTRL() [4/4]
```

```
const std::vector< idx > & ctrl_dits,
const std::vector< idx > & target,
std::string name = "" ) [inline]
```

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the
	classical control dits
name	Optional gate name

Returns

Reference to the current instance

7.54.5.9 cCTRL_custom()

Jointly applies the custom multiple-qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the qudit indexes specified by *target*.

Parameters

U	Multiple-qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit indexes where the gate U is applied depending on the values of the classical control dits
name	Optional gate name

Returns

Reference to the current instance

7.54.5.10 cend()

```
const_iterator qpp::QCircuitDescription::cend ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

Returns

Constant iterator to the next to the last element

Applies the single qudit controlled gate *U* with control qudit *ctrl* and target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.12 CTRL() [2/4]
```

Applies the single qudit controlled gate *U* with control qudit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.14 CTRL() [4/4]
```

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes; the gate <i>U</i> is applied on every one of them depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

7.54.5.15 CTRL_custom()

Jointly applies the custom multiple-qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the qudit indexes specified by *target*.

Parameters

U	Multiple-qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes where the gate U is applied depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

7.54.5.16 display()

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the quantum circuit description

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.54.5.17 end() [1/2]
```

```
iterator qpp::QCircuitDescription::end ( ) [inline]
```

Iterator to the next to the last element.

Returns

Iterator to the next to the last element

```
7.54.5.18 end() [2/2]
const_iterator qpp::QCircuitDescription::end ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

Returns

Constant iterator to the next to the last element

Applies the single qudit gate *U* on single qudit *i*.

Parameters

U	Single qudit quantum gate
i	Qudit index
name	Optional gate name

Returns

Reference to the current instance

```
idx i,
idx j,
std::string name = "" ) [inline]
```

Applies the two qudit gate *U* on qudits *i* and *j*.

Parameters

U	Two qudit quantum gate
i	Qudit index
j	Qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.21 gate() [3/3]
```

Applies the three qudit gate U on qudits i, j and k.

Parameters

U	Three qudit quantum gate
i	Qudit index
j	Qudit index
k	Qudit index
name	Optional gate name

Returns

Reference to the current instance

7.54.5.22 gate_custom()

Jointly applies the custom multiple qudit gate *U* on the qudit indexes specified by *target*.

Parameters

U	Multiple qudit quantum gate
target	Subsystem indexes where the gate U is applied
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit gate *U* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
target	Target qudit indexes; the gate <i>U</i> is applied on every one of them
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit gate $\it U$ on every remaining non-measured qudit.

Parameters

U	Single qudit quantum gate
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.25 get_d()
idx qpp::QCircuitDescription::get_d ( ) const [inline], [noexcept]
Local dimension of the comprising qudits.
Returns
     Local dimension
7.54.5.26 get_gate_count()
idx qpp::QCircuitDescription::get_gate_count ( ) const [inline], [noexcept]
Quantum circuit total gate count.
Returns
     Total gate count
7.54.5.27 get_gates()
const std::vector<GateStep>& qpp::QCircuitDescription::get_gates ( ) const [inline], [noexcept]
Vector of qpp::QCircuitDescription::GateStep.
Returns
     Vector of qpp::QCircuitDescription::GateStep
7.54.5.28 get_measured() [1/2]
idx qpp::QCircuitDescription::get_measured (
```

idx i) const [inline]

Check whether qudit i was already measured.

Parameters

i Qudit index

Returns

True if qudit i was already measured, false othwewise

```
7.54.5.29 get_measured() [2/2]
std::vector<idx> qpp::QCircuitDescription::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

```
7.54.5.30 get_measurement_count()
```

```
idx qpp::QCircuitDescription::get_measurement_count ( ) const [inline], [noexcept]
```

Quantum circuit total measurement count.

Returns

Total measurement count

7.54.5.31 get_measurement_steps()

```
std::vector<idx> qpp::QCircuitDescription::get_measurement_steps ( ) const [inline]
```

Vector of measurement positions in the circuit, i.e. the indexes where the measurements take place.

Note

If there are more consecutive measurements after step S, then their indexes will all be S, i.e. it is always assumed that the measurements taking place immediately after a gate step have the same index as the preceding gate step.

Returns

Vector of measurement positions

```
7.54.5.32 get_measurements()
```

```
const std::vector<MeasureStep>& qpp::QCircuitDescription::get_measurements ( ) const [inline],
[noexcept]
```

Vector of qpp::QCircuitDescription::MeasureStep.

Returns

Vector of qpp::QCircuitDescription::MeasureStep

```
7.54.5.33 get_name()
```

```
std::string qpp::QCircuitDescription::get_name ( ) const [inline]
```

Quantum circuit name.

Returns

Quantum circuit name

```
7.54.5.34 get_nc()
```

```
idx qpp::QCircuitDescription::get_nc ( ) const [inline], [noexcept]
```

Total number of classical dits in the circuit.

Returns

Total number of classical dits

```
7.54.5.35 get_non_measured()
```

```
\verb|std::vector<| idx>| qpp::QCircuitDescription::get_non_measured () const [inline]|
```

Vector of non-measured qudit indexes.

Returns

Vector of non-measured qudit indexes

7.54.5.36 get_nq()

```
idx qpp::QCircuitDescription::get_nq ( ) const [inline], [noexcept]
```

Total number of qudits in the circuit.

Returns

Total number of qudits

7.54.5.37 get_steps_count()

```
idx qpp::QCircuitDescription::get_steps_count ( ) const [inline], [noexcept]
```

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

Returns

Total (gates + measurements) count

7.54.5.38 measureV() [1/2]

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V
i	Qudit index
c_reg	Classical register where the value of the measurement is stored
name	Optional measurement name

Returns

Reference to the current instance

7.54.5.39 measureV() [2/2]

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix *V*.

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V
target	Target qudit indexes that are jointly measured
c_reg	Classical register where the value of the measurement is stored
name	Optional measurement name

Returns

Reference to the current instance

7.54.5.40 measureZ()

Measurement of single qudit in the computational basis (Z-basis)

Parameters

i	Qudit index
c_reg	Classical register where the value of the measurement is being stored
name	Optional measurement name, default is "Measure Z"

Returns

Reference to the current instance

7.54.5.41 QFT()

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

7.54.5.42 TFQ()

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the inverse quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

```
7.54.5.43 to_JSON()
```

```
std::string qpp::QCircuitDescription::to_JSON ( ) const [inline]
```

7.54.6 Friends And Related Function Documentation

Extraction operator overload for qpp::QCircuitDescription::GateType enum class.

Parameters

os	Output stream
gate_type	qpp::QCircuitDescription::GateType enum class

Returns

Output stream

Extraction operator overload for qpp::QCircuitDescription::MeasureType enum class.

Parameters

os	Output stream
gate_type	qpp::QCircuitDescription::MeasureType enum class

Returns

Output stream

Extraction operator overload for qpp::QCircuitDescription::GateStep class.

Parameters

os	Output stream
gate_type	qpp::QCircuitDescription::GateStep class

Returns

Output stream

```
7.54.6.4 operator << [4/4]

std::ostream& operator << (
    std::ostream & os,</pre>
```

Extraction operator overload for qpp::QCircuitDescription::MeasureStep class.

const MeasureStep & measure_step) [friend]

Parameters

os	Output stream
gate_type	qpp::QCircuitDescription::MeasureStep enum class

Returns

Output stream

7.54.7 Member Data Documentation

```
7.54.7.1 d_
const idx qpp::QCircuitDescription::d_ [private]

qudit dimension

7.54.7.2 gates_
std::vector<GateStep> qpp::QCircuitDescription::gates_ {} [private]

gates
```

std::vector<bool> qpp::QCircuitDescription::measured_ [private]

keeps track of the measured qudits

7.54.7.3 measured_

```
7.54.7.4 measurement_steps_
std::vector<idx> qpp::QCircuitDescription::measurement_steps_ {} [private]
measurements take place
keeps track of where the
7.54.7.5 measurements
std::vector<MeasureStep> qpp::QCircuitDescription::measurements_ {} [private]
measurements
7.54.7.6 name_
std::string qpp::QCircuitDescription::name_ [private]
optional circuit name
7.54.7.7 nc_
const idx qpp::QCircuitDescription::nc_ [private]
number of classical "dits"
7.54.7.8 nq_
const idx qpp::QCircuitDescription::nq_ [private]
number of qudits
7.54.7.9 steps_cnt_
idx qpp::QCircuitDescription::steps_cnt_ [private]
step counter
```

• classes/circuits.h


The documentation for this class was generated from the following file:

7.55 qpp::QubitAmplitudeDampingNoise Class Reference


Qubit amplitude damping noise, as described in Nielsen and Chuang.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitAmplitudeDampingNoise:



Collaboration diagram for qpp::QubitAmplitudeDampingNoise:



Public Member Functions

• QubitAmplitudeDampingNoise (double gamma)

Qubit amplitude damping noise constructor.

Additional Inherited Members

7.55.1 Detailed Description

Qubit amplitude damping noise, as described in Nielsen and Chuang.

7.55.2 Constructor & Destructor Documentation

7.55.2.1 QubitAmplitudeDampingNoise()

Qubit amplitude damping noise constructor.

Parameters

gamma	Amplitude damping probability
-------	-------------------------------

The documentation for this class was generated from the following file:


classes/noise.h

7.56 qpp::QubitBitFlipNoise Class Reference


Qubit bit flip noise.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitBitFlipNoise:



Collaboration diagram for qpp::QubitBitFlipNoise:



Public Member Functions

QubitBitFlipNoise (double p)
 Qubit bit flip noise constructor.

Additional Inherited Members

7.56.1 Detailed Description

Qubit bit flip noise.

7.56.2 Constructor & Destructor Documentation

7.56.2.1 QubitBitFlipNoise()

```
\label{eq:qpp::QubitBitFlipNoise} $$ \operatorname{qpp}::\operatorname{QubitBitFlipNoise} ($$ \operatorname{double} p ) [inline], [explicit] $$
```

Qubit bit flip noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.57 qpp::QubitBitPhaseFlipNoise Class Reference


Qubit bit-phase flip (dephasing) noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitBitPhaseFlipNoise:



Collaboration diagram for qpp::QubitBitPhaseFlipNoise:



Public Member Functions

QubitBitPhaseFlipNoise (double p)
 Qubit bit-phase flip noise constructor.

Additional Inherited Members

7.57.1 Detailed Description

Qubit bit-phase flip (dephasing) noise.

7.57.2 Constructor & Destructor Documentation

7.57.2.1 QubitBitPhaseFlipNoise()

```
\label{eq:qpp::QubitBitPhaseFlipNoise::QubitBitPhaseFlipNoise (} \\ \text{double } p \text{ ) } \quad \text{[inline], [explicit]}
```

Qubit bit-phase flip noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


classes/noise.h

7.58 qpp::QubitDepolarizingNoise Class Reference


Qubit depolarizing noise.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitDepolarizingNoise:



Collaboration diagram for qpp::QubitDepolarizingNoise:



Public Member Functions

QubitDepolarizingNoise (double p)
 Qubit depolarizing noise constructor.

Additional Inherited Members

7.58.1 Detailed Description

Qubit depolarizing noise.

7.58.2 Constructor & Destructor Documentation

7.58.2.1 QubitDepolarizingNoise()

```
\label{eq:qpp::QubitDepolarizingNoise::QubitDepolarizingNoise (} $$ double $p$ ) [inline], [explicit]
```

Qubit depolarizing noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.59 qpp::QubitPhaseDampingNoise Class Reference


Qubit phase damping noise, as described in Nielsen and Chuang.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitPhaseDampingNoise:



Collaboration diagram for qpp::QubitPhaseDampingNoise:



Public Member Functions

QubitPhaseDampingNoise (double lambda)
 Qubit phase damping noise constructor.

Additional Inherited Members

7.59.1 Detailed Description

Qubit phase damping noise, as described in Nielsen and Chuang.

7.59.2 Constructor & Destructor Documentation

7.59.2.1 QubitPhaseDampingNoise()

Qubit phase damping noise constructor.

Parameters

The documentation for this class was generated from the following file:


· classes/noise.h

7.60 qpp::QubitPhaseFlipNoise Class Reference


Qubit phase flip (dephasing) noise.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitPhaseFlipNoise:



Collaboration diagram for qpp::QubitPhaseFlipNoise:



Public Member Functions

• QubitPhaseFlipNoise (double p)

Qubit phase flip (dephasing) noise constructor.

Additional Inherited Members

7.60.1 Detailed Description

Qubit phase flip (dephasing) noise.

7.60.2 Constructor & Destructor Documentation

7.60.2.1 QubitPhaseFlipNoise()

Qubit phase flip (dephasing) noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


• classes/noise.h

7.61 qpp::exception::QuditAlreadyMeasured Class Reference


Qudit was already measured exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::QuditAlreadyMeasured:



Collaboration diagram for qpp::exception::QuditAlreadyMeasured:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.61.1 Detailed Description

Qudit was already measured exception.

The qudit was already measured and cannot be measured again

7.61.2 Member Function Documentation

7.61.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occur	urred
---	-------

7.61.2.2 type_description()

std::string qpp::exception::QuditAlreadyMeasured::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.62 qpp::QuditDepolarizingNoise Class Reference


Qudit depolarizing noise.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QuditDepolarizingNoise:



Collaboration diagram for qpp::QuditDepolarizingNoise:



Public Member Functions

QuditDepolarizingNoise (double p, idx d)
 Qudit depolarizing noise constructor.

Private Member Functions

- std::vector< cmat > fill_Ks_ (idx d) const
- std::vector< double > fill_probs_ (double p, idx d) const

Private Attributes

· const idx d_

Additional Inherited Members

7.62.1 Detailed Description

Qudit depolarizing noise.

7.62.2 Constructor & Destructor Documentation

7.62.2.1 QuditDepolarizingNoise()

```
qpp::QuditDepolarizingNoise::QuditDepolarizingNoise ( double p, idx d) [inline], [explicit]
```

Qudit depolarizing noise constructor.

Parameters

р	Noise probability
d	Subsystem dimension

7.62.3 Member Function Documentation

idx d) const [inline], [private]

7.62.4 Member Data Documentation

```
7.62.4.1 d_
const idx qpp::QuditDepolarizingNoise::d_ [private]
```

The documentation for this class was generated from the following file:


· classes/noise.h

7.63 qpp::RandomDevices Class Reference


Singleton class that manages the source of randomness in the library.

#include <classes/random_devices.h>

Inheritance diagram for qpp::RandomDevices:



Collaboration diagram for qpp::RandomDevices:



Public Member Functions

• std::mt19937 & get_prng ()

Returns a reference to the internal PRNG object.

• std::istream & load (std::istream &is)

Loads the state of the PRNG from an input stream.

• std::ostream & save (std::ostream &os) const

Saves the state of the PRNG to an output stream.

Private Member Functions

• RandomDevices ()

Initializes and seeds the random number generators.

∼RandomDevices ()=default

Default destructor.

Private Attributes

 std::random_device rd_ used to seed std::mt19937 prng_

std::mt19937 prng_

Mersenne twister random number generator.

Friends

class internal::Singleton < RandomDevices >

Additional Inherited Members

7.63.1 Detailed Description

Singleton class that manages the source of randomness in the library.

Consists of a wrapper around an std::mt19937 Mersenne twister random number generator engine and an std

∴ random_device engine. The latter is used to seed the Mersenne twister.

Warning

This class DOES NOT seed the standard C number generator used by Eigen::Matrix::Random(), since it is not thread safe. Do not use Eigen::Matrix::Random() or functions that depend on the C style random number engine, but use qpp::rand() instead!

7.63.2 Constructor & Destructor Documentation

7.63.2.1 RandomDevices()

```
qpp::RandomDevices::RandomDevices ( ) [inline], [private]
```

Initializes and seeds the random number generators.

7.63.2.2 ~RandomDevices()

```
\verb"qpp::RandomDevices::$\sim$RandomDevices ( ) [private], [default]
```

Default destructor.

7.63.3 Member Function Documentation

```
7.63.3.1 get_prng()
```

```
std::mt19937& qpp::RandomDevices::get_prng ( ) [inline]
```

Returns a reference to the internal PRNG object.

Returns

Reference to the internal PRNG object

7.63.3.2 load()

Loads the state of the PRNG from an input stream.

Parameters

```
is Input stream
```

Returns

The input stream

7.63.3.3 save()

Saves the state of the PRNG to an output stream.

Parameters

os Output stream

Returns

The output stream

7.63.4 Friends And Related Function Documentation

```
7.63.4.1 internal::Singleton < Random Devices >
```

```
friend class internal::Singleton< RandomDevices > [friend]
```

7.63.5 Member Data Documentation

```
7.63.5.1 prng_
```

```
std::mt19937 qpp::RandomDevices::prng_ [private]
```

Mersenne twister random number generator.

```
7.63.5.2 rd_
```

```
std::random_device qpp::RandomDevices::rd_ [private]
```

used to seed std::mt19937 prng_

The documentation for this class was generated from the following file:

• classes/random_devices.h

7.64 qpp::internal::Singleton < T > Class Template Reference

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

```
#include <internal/classes/singleton.h>
```

Static Public Member Functions

- static T & get_instance () noexcept(std::is_nothrow_constructible < T >::value)
- static T & get_thread_local_instance () noexcept(std::is_nothrow_constructible < T >::value)

Protected Member Functions

- Singleton () noexcept=default
- Singleton (const Singleton &)=delete
- Singleton & operator= (const Singleton &)=delete
- virtual ∼Singleton ()=default

7.64.1 Detailed Description

```
\label{template} \begin{tabular}{ll} template < typename T > \\ class & qpp::internal::Singleton < T > \\ \end{tabular}
```

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

To implement a singleton, derive your class from qpp::internal::Singleton, make qpp::internal::Singleton a friend of your class, then declare the constructor and destructor of your class as private. To get an instance, use the static member function qpp::internal::Singleton::get_instance() (qpp::internal::Singleton::get_thread_local_instance()), which returns a reference (thread_local_reference) to your newly created singleton (thread-safe in C++11).

Example:

See also

Code of qpp::Codes, qpp::Gates, qpp::Init, qpp::RandomDevices, qpp::States or qpp.h for real world examples of usage.

7.64.2 Constructor & Destructor Documentation

```
7.64.2.1 Singleton() [1/2]
template<typename T>
qpp::internal::Singleton < T >::Singleton ( ) [protected], [default], [noexcept]
7.64.2.2 Singleton() [2/2]
template<typename T>
qpp::internal::Singleton < T >::Singleton (
            const Singleton< T > \& ) [protected], [delete]
7.64.2.3 ∼Singleton()
template<typename T>
virtual qpp::internal::Singleton < T >::~Singleton ( ) [protected], [virtual], [default]
7.64.3 Member Function Documentation
7.64.3.1 get_instance()
template<typename T>
\texttt{static T\& qpp::internal::Singleton} < \texttt{T} > :: \texttt{get\_instance ()} \quad \texttt{[inline], [static], [noexcept]}
7.64.3.2 get_thread_local_instance()
template<typename T>
static T& qpp::internal::Singleton< T >::get_thread_local_instance ( ) [inline], [static],
[noexcept]
7.64.3.3 operator=()
template<typename T>
Singleton& qpp::internal::Singleton< T >::operator= (
             const Singleton< T > \& ) [protected], [delete]
```

The documentation for this class was generated from the following file:


• internal/classes/singleton.h

7.65 qpp::exception::SizeMismatch Class Reference


Size mismatch exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SizeMismatch:



Collaboration diagram for qpp::exception::SizeMismatch:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.65.1 Detailed Description

Size mismatch exception.

Sizes do not match

7.65.2 Member Function Documentation

7.65.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.65.2.2 type_description()

```
std::string qpp::exception::SizeMismatch::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

7.66 qpp::NoiseType::StateDependent Class Reference

Template tag, used whenever the noise is state-dependent.

#include <classes/noise.h>

7.66.1 Detailed Description

Template tag, used whenever the noise is state-dependent.

The documentation for this class was generated from the following file:

· classes/noise.h

7.67 qpp::NoiseType::StateIndependent Class Reference

Template tag, used whenever the noise is state-independent.

#include <classes/noise.h>

7.67.1 Detailed Description

Template tag, used whenever the noise is state-independent.

The documentation for this class was generated from the following file:


classes/noise.h

7.68 qpp::States Class Reference


const Singleton class that implements most commonly used states

#include <classes/states.h>

Inheritance diagram for qpp::States:



Collaboration diagram for qpp::States:



Public Member Functions

• ket mes (idx d=2) const

Maximally entangled state of 2 qudits.

• ket zero (idx n, idx d=2) const

Zero state of n qudits.

• ket one (idx n, idx d=2) const

One state of n qudits.

• ket jn (idx j, idx n, idx d=2) const

 $|j\rangle^{\otimes n}$ state of n qudits

• ket plus (idx n) const

Plus state of n qubits.

• ket minus (idx n) const

Minus state of n qubits.

Public Attributes

```
    ket x0 {ket::Zero(2)}
```

Pauli Sigma-X 0-eigenstate |+>

ket x1 {ket::Zero(2)}

Pauli Sigma-X 1-eigenstate |->

ket y0 {ket::Zero(2)}

Pauli Sigma-Y 0-eigenstate |y+>

ket y1 {ket::Zero(2)}

Pauli Sigma-Y 1-eigenstate | y->

ket z0 {ket::Zero(2)}

Pauli Sigma-Z 0-eigenstate |0>

ket z1 {ket::Zero(2)}

Pauli Sigma-Z 1-eigenstate | 1>

cmat px0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

• cmat px1 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.

```
    cmat py0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 0-eigenstate |y+\rangle < y+|.

    cmat py1 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.

    cmat pz0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
• cmat pz1 {cmat::Zero(2, 2)}
      Projector onto the Pauli Sigma-Z 1-eigenstate | 1><1|.
ket b00 {ket::Zero(4)}
      Bell-00 state, as described in Nielsen and Chuang.

    ket b01 {ket::Zero(4)}

      Bell-01 state, as described in Nielsen and Chuang.

    ket b10 {ket::Zero(4)}

      Bell-10 state, as described in Nielsen and Chuang.
ket b11 {ket::Zero(4)}
      Bell-11 state, as described in Nielsen and Chuang.

    cmat pb00 {cmat::Zero(4, 4)}

      Projector onto the Bell-00 state.

    cmat pb01 {cmat::Zero(4, 4)}

      Projector onto the Bell-01 state.

    cmat pb10 {cmat::Zero(4, 4)}

      Projector onto the Bell-10 state.

    cmat pb11 {cmat::Zero(4, 4)}

      Projector onto the Bell-11 state.
ket GHZ {ket::Zero(8)}
      GHZ state.

    ket W {ket::Zero(8)}

      W state.
cmat pGHZ {cmat::Zero(8, 8)}
      Projector onto the GHZ state.
cmat pW {cmat::Zero(8, 8)}
```

Private Member Functions

- States ()
- ∼States ()=default

Default destructor.

Projector onto the W state.

Friends

class internal::Singleton < const States >

Additional Inherited Members

7.68.1 Detailed Description

const Singleton class that implements most commonly used states

7.68.2 Constructor & Destructor Documentation

```
7.68.2.1 States()

qpp::States::States ( ) [inline], [private]

Initialize the states

7.68.2.2 ~States()

qpp::States::~States ( ) [private], [default]
```

7.68.3 Member Function Documentation

```
7.68.3.1 jn()
```

Default destructor.

 $|j\rangle^{\otimes n}$ state of *n* qudits

Parameters

j	Non-negative integer
n	Non-negative integer
d	Subsystem dimensions

Returns

 $|j\rangle^{\otimes n}$ state of *n* qudits

7.68.3.2 mes()

```
ket qpp::States::mes (
idx d = 2 ) const [inline]
```

Maximally entangled state of 2 qudits.

Parameters

d Subsystem dimensions

Returns

Maximally entangled state $\frac{1}{\sqrt{d}} \sum_{j=0}^{d-1} |jj\rangle$ of 2 qudits

7.68.3.3 minus()

```
ket qpp::States::minus (
          idx n ) const [inline]
```

Minus state of n qubits.

Parameters

n Non-negative integer

Returns

Minus state $|-\rangle^{\otimes n}$ of n qubits

7.68.3.4 one()

```
ket qpp::States::one (
        idx n,
        idx d = 2 ) const [inline]
```

One state of *n* qudits.

Parameters

n	Non-negative integer
d	Subsystem dimensions

Returns

One state $|1\rangle^{\otimes n}$ of n qudits

```
7.68.3.5 plus()
```

```
ket qpp::States::plus (
         idx n ) const [inline]
```

Plus state of *n* qubits.

Parameters

```
n Non-negative integer
```

Returns

Plus state $|+\rangle^{\otimes n}$ of n qubits

7.68.3.6 zero()

```
ket qpp::States::zero (
         idx n,
         idx d = 2 ) const [inline]
```

Zero state of *n* qudits.

Parameters

n	Non-negative integer
d	Subsystem dimensions

Returns

Zero state $|0\rangle^{\otimes n}$ of n qudits

7.68.4 Friends And Related Function Documentation

```
7.68.4.1 internal::Singleton < const States >
```

```
friend class internal::Singleton< const States > [friend]
```

7.68.5 Member Data Documentation

```
7.68.5.1 b00
```

```
ket qpp::States::b00 {ket::Zero(4)}
```

Bell-00 state, as described in Nielsen and Chuang.

```
7.68.5.2 b01
```

```
ket qpp::States::b01 {ket::Zero(4)}
```

Bell-01 state, as described in Nielsen and Chuang.

```
7.68.5.3 b10
```

```
ket qpp::States::b10 {ket::Zero(4)}
```

Bell-10 state, as described in Nielsen and Chuang.

7.68.5.4 b11

```
ket qpp::States::b11 {ket::Zero(4)}
```

Bell-11 state, as described in Nielsen and Chuang.

7.68.5.5 GHZ

```
ket qpp::States::GHZ {ket::Zero(8)}
```

GHZ state.

7.68.5.6 pb00

```
cmat qpp::States::pb00 {cmat::Zero(4, 4)}
```

Projector onto the Bell-00 state.

```
7.68.5.7 pb01
cmat qpp::States::pb01 {cmat::Zero(4, 4)}
Projector onto the Bell-01 state.
7.68.5.8 pb10
cmat qpp::States::pb10 {cmat::Zero(4, 4)}
Projector onto the Bell-10 state.
7.68.5.9 pb11
cmat qpp::States::pb11 {cmat::Zero(4, 4)}
Projector onto the Bell-11 state.
7.68.5.10 pGHZ
cmat qpp::States::pGHZ {cmat::Zero(8, 8)}
Projector onto the GHZ state.
7.68.5.11 pW
cmat qpp::States::pW {cmat::Zero(8, 8)}
Projector onto the W state.
7.68.5.12 px0
```

cmat qpp::States::px0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

```
7.68.5.13 px1
cmat qpp::States::px1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.
7.68.5.14 py0
cmat qpp::States::py0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 0-eigenstate |y+>< y+|.
7.68.5.15 py1
cmat qpp::States::py1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.
7.68.5.16 pz0
cmat qpp::States::pz0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
7.68.5.17 pz1
cmat qpp::States::pz1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 1-eigenstate |1><1|.
7.68.5.18 W
ket qpp::States::W {ket::Zero(8)}
```

W state.

```
7.68.5.19 x0
ket qpp::States::x0 {ket::Zero(2)}
Pauli Sigma-X 0-eigenstate |+>
7.68.5.20 x1
ket qpp::States::x1 {ket::Zero(2)}
Pauli Sigma-X 1-eigenstate |->
7.68.5.21 y0
ket qpp::States::y0 {ket::Zero(2)}
Pauli Sigma-Y 0-eigenstate |y+>
7.68.5.22 y1
ket qpp::States::y1 {ket::Zero(2)}
Pauli Sigma-Y 1-eigenstate |y->
7.68.5.23 z0
ket qpp::States::z0 {ket::Zero(2)}
Pauli Sigma-Z 0-eigenstate |0>
7.68.5.24 z1
ket qpp::States::z1 {ket::Zero(2)}
Pauli Sigma-Z 1-eigenstate |1>
The documentation for this class was generated from the following file:
```


· classes/states.h

7.69 qpp::exception::SubsysMismatchDims Class Reference


Subsystems mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SubsysMismatchDims:



Collaboration diagram for qpp::exception::SubsysMismatchDims:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.69.1 Detailed Description

Subsystems mismatch dimensions exception.

std::vector<idx> of subsystem labels has duplicates, or has entries that are larger than the size of the std← ::vector<idx> of dimensions

7.69.2 Member Function Documentation

7.69.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred
--

7.69.2.2 type_description()

```
std::string qpp::exception::SubsysMismatchDims::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.70 qpp::Timer < T, CLOCK_T > Class Template Reference


Chronometer.

#include <classes/timer.h>

Inheritance diagram for qpp::Timer< T, CLOCK_T >:



Collaboration diagram for qpp::Timer < T, CLOCK_T >:



Public Member Functions

• Timer () noexcept

Constructs an instance with the current time as the starting point.

• void tic () noexcept

Resets the chronometer.

• const Timer & toc () noexcept

Stops the chronometer.

• double tics () const noexcept

Time passed in the duration specified by T.

• template<typename U = T>

U get_duration () const noexcept

Duration specified by U.

• Timer (const Timer &)=default

Default copy constructor.

• Timer (Timer &&)=default

Default move constructor.

• Timer & operator= (const Timer &)=default

Default copy assignment operator.

• Timer & operator= (Timer &&)=default

Default move assignment operator.

virtual ∼Timer ()=default

Default virtual destructor.

Protected Attributes

- CLOCK_T::time_point start_
- CLOCK_T::time_point end_

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display() override*

7.70.1 Detailed Description

```
template < typename\ T = std::chrono::duration < double >, typename\ CLOCK\_T = std::chrono::steady\_clock > class\ qpp::Timer < T,\ CLOCK\_T >
```

Chronometer.

Template Parameters

T	Tics duration, default is std::chrono::duration <double, 1="">, i.e. seconds in double precision</double,>
CLOCK← T	Clock's type, default is std::chrono::steady_clock, not affected by wall clock changes during runtime

7.70.2 Constructor & Destructor Documentation

```
7.70.2.1 Timer() [1/3]
```

```
\label{template} $$ \ensuremath{\texttt{template}}$ $$ \ensuremath{\texttt{typename T = std::chrono::steady}}$ $$ $$ \ensuremath{\texttt{clock}}$ $$ \ensuremath{\texttt{clock}}$ $$ $$ \ensuremath{\texttt{qpp::Timer}}$ $$ \ensuremath{\texttt{T, CLOCK\_T >::Timer}}$ ( ) [inline], [noexcept] $$
```

Constructs an instance with the current time as the starting point.

7.70.2.2 Timer() [2/3]

Default copy constructor.

```
7.70.2.3 Timer() [3/3]
```

Default move constructor.

7.70.2.4 \sim Timer()

```
\label{template} $$ \ensuremath{\sf template}$ $$ \ensurem
```

Default virtual destructor.

7.70.3 Member Function Documentation

7.70.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream the number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc().

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.70.3.2 get_duration()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady 
_clock>
template<typename U = T>
U qpp::Timer< T, CLOCK_T >::get_duration ( ) const [inline], [noexcept]
```

Duration specified by U.

Template Parameters

U Duration, default is T, which defaults to std::chrono::duration<double, 1>, i.e. seconds in double precision

Returns

Duration that passed between the instantiation/reset and invocation of qpp::Timer::toc()

7.70.3.3 operator=() [1/2]

Default copy assignment operator.

7.70.3.4 operator=() [2/2]

Default move assignment operator.

7.70.3.5 tic()

```
 \begin{tabular}{ll} template < type name T = std::chrono::duration < double>, type name CLOCK_T = std::chrono::steady & clock> \\ void qpp::Timer < T, CLOCK_T >::tic ( ) [inline], [noexcept] \\ \end{tabular}
```

Resets the chronometer.

Resets the starting/ending point to the current time

7.70.3.6 tics()

```
 \begin{tabular}{ll} template < typename T = std::chrono::duration < double >, typename CLOCK_T = std::chrono::steady \leftarrow \_clock > \\ double qpp::Timer < T, CLOCK_T >::tics ( ) const [inline], [noexcept] \\ \end{tabular}
```

Time passed in the duration specified by T.

Returns

Number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc()

7.70.3.7 toc()

```
 \begin{tabular}{ll} template < type name $T = std::chrono::steady \leftarrow \_clock > \\ const $Timer\& $qpp::Timer < T, $CLOCK_T > ::toc ( ) [inline], [noexcept] \end{tabular}
```

Stops the chronometer.

Set the current time as the ending point

Returns

Reference to the current instance

7.70.4 Member Data Documentation

7.70.4.1 end

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady←
   _clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::end_ [protected]
```

7.70.4.2 start_

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::start_ [protected]
```

The documentation for this class was generated from the following file:


· classes/timer.h

7.71 qpp::exception::TypeMismatch Class Reference


Type mismatch exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::TypeMismatch:



Collaboration diagram for qpp::exception::TypeMismatch:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.71.1 Detailed Description

Type mismatch exception.

Scalar types do not match

7.71.2 Member Function Documentation

7.71.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred
--

7.71.2.2 type_description()

std::string qpp::exception::TypeMismatch::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.72 qpp::exception::UndefinedType Class Reference


Not defined for this type exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::UndefinedType:



Collaboration diagram for qpp::exception::UndefinedType:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.72.1 Detailed Description

Not defined for this type exception.

Templated specialization is not defined for this type

7.72.2 Member Function Documentation

7.72.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred	
--	--

7.72.2.2 type_description()

std::string qpp::exception::UndefinedType::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.73 qpp::exception::Unknown Class Reference


Unknown exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::Unknown:



Collaboration diagram for qpp::exception::Unknown:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.73.1 Detailed Description

Unknown exception.

Thrown when no other exception is suitable (not recommended, it is better to define another suitable exception type)

7.73.2 Member Function Documentation

7.73.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occur	urred
---	-------

7.73.2.2 type_description()

 $\verb|std::string|| qpp::exception::Unknown::type_description|| () | const|| [inline], [override], [virtual]|| () | const|| ()$

Exception type description.

Returns

Exception type description


Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.74 qpp::QCircuitDescription::iterator::value_type_ Struct Reference

Inheritance diagram for qpp::QCircuitDescription::iterator::value_type_:



 $Collaboration\ diagram\ for\ qpp:: QCircuit Description:: iterator:: value_type_:$



Public Member Functions

```
    value_type_ (const value_type_ &)=default
    Default copy constructor.
```

value_type_ & operator= (const value_type_ &)=default
 Default copy assignment operator.

- value type (const QCircuitDescription *value type qcd)
- std::ostream & display (std::ostream &os) const override

```
qpp::IDisplay::display() override
```

Public Attributes

```
bool is_measurement_ {false}
```

current step is a measurement

• idx m_ip_ {idx_infty}

measurements instruction pointer

idx q_ip_ {idx_infty}

gates instruction pointer

idx ip_ {idx_infty}pointer

const QCircuitDescription * value_type_qcd_

7.74.1 Constructor & Destructor Documentation

Default copy constructor.

7.74.2 Member Function Documentation

qpp::IDisplay::display() override

Writes to the output stream the textual representation of the iterator de-referenced element

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.74.2.2 operator=()

Default copy assignment operator.

Returns

Reference to the current instancenon-owning pointer to the parent iterator

7.74.3 Member Data Documentation

```
7.74.3.1 ip_
idx qpp::QCircuitDescription::iterator::value_type_::ip_ {idx_infty}

pointer

total (measurements + gates) instruction

7.74.3.2 is_measurement_
bool qpp::QCircuitDescription::iterator::value_type_::is_measurement_ {false}

current step is a measurement

7.74.3.3 m_ip_
idx qpp::QCircuitDescription::iterator::value_type_::m_ip_ {idx_infty}
```

measurements instruction pointer

7.74.3.4 q_ip_

```
idx qpp::QCircuitDescription::iterator::value_type_::q_ip_ {idx_infty}
```

gates instruction pointer

7.74.3.5 value_type_qcd_

```
const QCircuitDescription* qpp::QCircuitDescription::iterator::value_type_::value_type_qcd_
```

The documentation for this struct was generated from the following file:


· classes/circuits.h

7.75 qpp::exception::ZeroSize Class Reference


Object has zero size exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::ZeroSize:



Collaboration diagram for qpp::exception::ZeroSize:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.75.1 Detailed Description

Object has zero size exception.

Zero sized object, e.g. empty Eigen::Matrix or std::vector with no elements

7.75.2 Member Function Documentation

7.75.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.75.2.2 type_description()

std::string qpp::exception::ZeroSize::type_description () const [inline], [override], [virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

• classes/exception.h


Chapter 8

File Documentation

8.1 classes/circuits.h File Reference

Support for qudit quantum circuits.

This graph shows which files directly or indirectly include this file:



Classes

- · class qpp::QCircuitDescription
 - Quantum circuit description class.
- class qpp::QCircuitDescription::iterator
 - Quantum circuit description bound-checking (safe) iterator.
- struct qpp::QCircuitDescription::iterator::value_type_
- struct qpp::QCircuitDescription::GateStep
 - One step consisting only of gates/operators in the circuit.
- struct qpp::QCircuitDescription::MeasureStep
 - One step consisting only of measurements in the circuit.
- class qpp::IQCircuit
 - Quantum circuit simulator abstract class.
- class qpp::QCircuit
 - Quantum circuit simulator class.

354 File Documentation

Namespaces

• qpp

Quantum++ main namespace.


8.1.1 Detailed Description

Support for qudit quantum circuits.

8.2 classes/codes.h File Reference

Quantum error correcting codes.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::Codes

const Singleton class that defines quantum error correcting codes

Namespaces

• qpp

Quantum++ main namespace.


8.2.1 Detailed Description

Quantum error correcting codes.

8.3 classes/exception.h File Reference

Exceptions.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::exception::Exception

Base class for generating Quantum++ custom exceptions.

· class qpp::exception::Unknown

Unknown exception.

class qpp::exception::ZeroSize

Object has zero size exception.

• class qpp::exception::MatrixNotSquare

Matrix is not square exception.

class qpp::exception::MatrixNotCvector

Matrix is not a column vector exception.

· class qpp::exception::MatrixNotRvector

Matrix is not a row vector exception.class qpp::exception::MatrixNotVector

Matrix is not a vector exception.

class qpp::exception::MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

• class qpp::exception::MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

class qpp::exception::MatrixNotSquareNorVector

Matrix is not square nor vector exception.

class qpp::exception::MatrixMismatchSubsys

Matrix mismatch subsystems exception.

· class qpp::exception::DimsInvalid

Invalid dimension(s) exception.

class qpp::exception::DimsNotEqual

Dimensions not equal exception.

class qpp::exception::DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

class qpp::exception::DimsMismatchCvector

356 File Documentation

Dimension(s) mismatch column vector size exception.

· class qpp::exception::DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

· class qpp::exception::DimsMismatchVector

Dimension(s) mismatch vector size exception.

class qpp::exception::SubsysMismatchDims

Subsystems mismatch dimensions exception.

· class qpp::exception::PermInvalid

Invalid permutation exception.

class qpp::exception::PermMismatchDims

Permutation mismatch dimensions exception.

· class qpp::exception::NotQubitMatrix

Matrix is not 2 x 2 exception.

· class qpp::exception::NotQubitCvector

Column vector is not 2 x 1 exception.

· class qpp::exception::NotQubitRvector

Row vector is not 1 x 2 exception.

· class qpp::exception::NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

• class qpp::exception::NotQubitSubsys

Subsystems are not qubits exception.

class gpp::exception::NotBipartite

Not bi-partite exception.

· class qpp::exception::NoCodeword

Codeword does not exist exception.

· class qpp::exception::OutOfRange

Argument out of range exception.

· class qpp::exception::TypeMismatch

Type mismatch exception.

class qpp::exception::SizeMismatch

Size mismatch exception.

class qpp::exception::UndefinedType

Not defined for this type exception.

· class qpp::exception::QuditAlreadyMeasured

Qudit was already measured exception.

· class qpp::exception::Duplicates

System (e.g. std::vector) has duplicates exception.

· class qpp::exception::CustomException

Custom exception.

· class qpp::exception::NotImplemented

Code not yet implemented.

· class qpp::exception::InvalidIterator

Invalid iterator.

Namespaces

qpp

Quantum++ main namespace.

qpp::exception

Quantum++ exception hierarchy namespace.


8.3.1 Detailed Description

Exceptions.

8.4 classes/gates.h File Reference

Quantum gates.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::Gates

const Singleton class that implements most commonly used gates

Namespaces

• qpp

Quantum++ main namespace.

8.4.1 Detailed Description


Quantum gates.

358 File Documentation

8.5 classes/idisplay.h File Reference

Display interface via the non-virtual interface (NVI)

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

Namespaces

qpp

Quantum++ main namespace.


8.5.1 Detailed Description

Display interface via the non-virtual interface (NVI)

8.6 classes/init.h File Reference

Initialization.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::Init

const Singleton class that performs additional initializations/cleanups

Namespaces

• qpp

Quantum++ main namespace.


8.6.1 Detailed Description

Initialization.

8.7 classes/noise.h File Reference

Noise models.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::NoiseType

Contains template tags used to specify the noise type.

class qpp::NoiseBase< T >

Base class for all noise models, derive your particular noise model.

class qpp::QubitDepolarizingNoise

Qubit depolarizing noise.

· class qpp::QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

• class qpp::QubitBitFlipNoise

Qubit bit flip noise.

· class qpp::QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

· class qpp::QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

· class qpp::QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

· class qpp::QuditDepolarizingNoise

Qudit depolarizing noise.

360 File Documentation

Namespaces

• qpp

Quantum++ main namespace.


8.7.1 Detailed Description

Noise models.

8.8 classes/random_devices.h File Reference

Random devices.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::RandomDevices

Singleton class that manages the source of randomness in the library.

Namespaces

• qpp

Quantum++ main namespace.


8.8.1 Detailed Description

Random devices.

8.9 classes/reversible.h File Reference

Support for classical reversible circuits.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::Dynamic_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

class qpp::Bit_circuit

Classical reversible circuit simulator.

• struct qpp::Bit_circuit::Gate_count

Namespaces

qpp

Quantum++ main namespace.


8.9.1 Detailed Description

Support for classical reversible circuits.

8.10 classes/states.h File Reference

Quantum states.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::States

const Singleton class that implements most commonly used states

Namespaces

• qpp

Quantum++ main namespace.


8.10.1 Detailed Description

Quantum states.

8.11 classes/timer.h File Reference

Timing.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::Timer < T, CLOCK_T >
 Chronometer.

Namespaces

• qpp

Quantum++ main namespace.


8.11.1 Detailed Description

Timing.

8.12 constants.h File Reference

Constants.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

• qpp::literals

Functions

- constexpr cplx qpp::literals::operator"" _i (unsigned long long int x) noexcept User-defined literal for complex $i=\sqrt{-1}$ (integer overload)
- constexpr cplx qpp::operator"" _i (long double x) noexcept

User-defined literal for complex $i = \sqrt{-1}$ (real overload)

• cplx qpp::omega (idx D)

D-th root of unity.

Variables

• constexpr double qpp::chop = 1e-10

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

• constexpr double qpp::eps = std::numeric_limits<double>::epsilon()

Used to decide whether a number or expression in double precision is zero or not for the purpose of a specific computation.

constexpr idx qpp::maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

• constexpr double qpp::pi = 3.141592653589793238462643383279502884

• constexpr double qpp::ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

constexpr double qpp::infty = std::numeric_limits<double>::max()

Used to denote infinity in double precision.

• const idx qpp::idx_infty = static_cast<idx>(-1)

Used to denote the largest unsigned index.


8.12.1 Detailed Description

Constants.

8.13 entanglement.h File Reference

Entanglement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

```
template<typename Derived >
  dyn col vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector<
  idx > &dims)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  dyn_col_vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  cmat qpp::schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat qpp::schmidtA (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Bob side.
template<typename Derived >
  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Bob side.
• template<typename Derived >
  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx
  > &dims)
      Schmidt probabilities of the bi-partite pure state A.

    template<typename Derived >

  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt probabilities of the bi-partite pure state A.
• template<typename Derived >
  double qpp::entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Entanglement of the bi-partite pure state A.
• template<typename Derived >
  double <a href="mailto:qpp::entanglement">qpp::entanglement</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Entanglement of the bi-partite pure state A.

    template<typename Derived >

  double <a href="mailto:qpp::gconcurrence">qpp::gconcurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      G-concurrence of the bi-partite pure state A.

    template<typename Derived >

  double qpp::negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double <a href="mailto:qpp::negativity">qpp::negativity</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double <a href="mailto:qpp::concurrence">qpp::concurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.
```


8.13.1 Detailed Description

Entanglement functions.

8.14 entropies.h File Reference

Entropy functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

```
    template<typename Derived >
        double qpp::entropy (const Eigen::MatrixBase< Derived > &A)
```

von-Neumann entropy of the density matrix A

double qpp::entropy (const std::vector< double > &prob)

Shannon entropy of the probability distribution prob.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

```
double qpp::renyi (const Eigen::MatrixBase< Derived > &A, double alpha)
```

Renyi- α entropy of the density matrix A, for $\alpha \geq 0$.

double qpp::renyi (const std::vector< double > &prob, double alpha)

Renyi- α entropy of the probability distribution prob, for $\alpha \geq 0$.

template<typename Derived >

```
double qpp::tsallis (const Eigen::MatrixBase< Derived > &A, double q)
```

Tsallis- q entropy of the density matrix A, for $q \geq 0$.

double qpp::tsallis (const std::vector< double > &prob, double q)

Tsallis- q entropy of the probability distribution prob, for $q \geq 0$.

• template<typename Derived >

double qpp::qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const std::vector< idx > &subsysB, const std::vector< idx > &dims)

Quantum mutual information between 2 subsystems of a composite system.

• template<typename Derived >

 $\label{lem:double qpp::qmutualinfo} $$ double qpp::qmutualinfo (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &subsysA, const std::vector < idx > &subsysB, idx d=2) \\$

Quantum mutual information between 2 subsystems of a composite system.

8.14.1 Detailed Description

Entropy functions.

8.15 experimental/experimental.h File Reference

Experimental/test functions/classes.

Namespaces

• qpp

Quantum++ main namespace.

· qpp::experimental

Experimental/test functions/classes, do not use or modify.


8.15.1 Detailed Description

Experimental/test functions/classes.

8.16 functions.h File Reference

Generic quantum computing functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

qpp::literals

Functions

```
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::transpose (const Eigen::MatrixBase< Derived > &A)
• template<typename Derived >
  dyn mat< typename Derived::Scalar > qpp::conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::adjoint (const Eigen::MatrixBase< Derived > &A)
      Adjoint.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::inverse (const Eigen::MatrixBase< Derived > &A)
      Inverse.

    template<typename Derived >

  Derived::Scalar qpp::trace (const Eigen::MatrixBase < Derived > &A)
• template<typename Derived >
  Derived::Scalar <a href="mailto:qpp::det">qpp::det</a> (const Eigen::MatrixBase</a> Derived > &A)

    template<typename Derived >

  Derived::Scalar qpp::logdet (const Eigen::MatrixBase< Derived > &A)
     Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar <a href="mailto:qpp::sum">qpp::sum</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise sum of A.
template<typename Derived >
  Derived::Scalar <a href="mailto:open:prod">open:prod</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise product of A.

    template<typename Derived >

  double <a href="mailto:qpp::norm">qpp::norm</a> (const Eigen::MatrixBase< Derived > &A)
      Frobenius norm.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::normalize (const Eigen::MatrixBase< Derived > &A)
      Normalizes state vector (column or row vector) or density matrix.
• template<typename Derived >
  std::pair< dyn_col_vect< cplx >, cmat > qpp::eig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition.
• template<typename Derived >
  dyn_col_vect< cplx > qpp::evals (const Eigen::MatrixBase< Derived > &A)
     Eigenvalues.

    template<typename Derived >

  cmat qpp::evects (const Eigen::MatrixBase< Derived > &A)
      Eigenvectors.

    template<typename Derived >

  std::pair< dyn_col_vect< double >, cmat > qpp::heig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > qpp::hevals (const Eigen::MatrixBase< Derived > &A)
      Hermitian eigenvalues.
• template<typename Derived >
  cmat qpp::hevects (const Eigen::MatrixBase< Derived > &A)
      Eigenvectors of Hermitian matrix.
```

```
• template<typename Derived >
  std::tuple< cmat, dyn_col_vect< double >, cmat > qpp::svd (const Eigen::MatrixBase< Derived > &A)
     Full singular value decomposition.

    template<typename Derived >

  dyn_col_vect< double > qpp::svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.
• template<typename Derived >
  cmat qpp::svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.

    template<typename Derived >

  cmat qpp::svdV (const Eigen::MatrixBase< Derived > &A)
     Right singular vectors.

    template<typename Derived >

  cmat qpp::funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)

    template < typename Derived >

  cmat qpp::sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.
• template<typename Derived >
  cmat qpp::absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.

    template<typename Derived >

  cmat qpp::expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.
• template<typename Derived >
  cmat qpp::logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.
• template<typename Derived >
  cmat <a href="mailto:qpp::sinm">qpp::sinm</a> (const Eigen::MatrixBase</a> Derived > &A)
     Matrix sin.
• template<typename Derived >
  cmat qpp::cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.
• template<typename Derived >
  cmat qpp::spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.
template<typename Derived >
  dyn mat< typename Derived::Scalar > qpp::powm (const Eigen::MatrixBase< Derived > &A, idx n)
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

    template<typename Derived >

  double qpp::schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > qpp::cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const
  typename Derived::Scalar &))
     Functor.

    template<typename T >

  dyn_mat< typename T::Scalar > qpp::kron (const T &head)
     Kronecker product.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > qpp::kron (const T &head, const Args &... tail)
     Kronecker product.
```

```
    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::kron (const std::vector< Derived > &As)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::kron (const std::initializer list< Derived > &As)
     Kronecker product.
template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Kronecker power.
• template<typename T >
  dyn_mat< typename T::Scalar > qpp::dirsum (const T &head)
     Direct sum.
• template<typename T , typename... Args>
  dyn mat< typename T::Scalar > qpp::dirsum (const T &head, const Args &... tail)
     Direct sum.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::vector< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::initializer_list< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::reshape (const Eigen::MatrixBase< Derived > &A, idx rows,
  idx cols)
     Reshape.

    template < typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > qpp::comm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Commutator.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > qpp::anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::prj (const Eigen::MatrixBase< Derived > &A)
     Projector.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::grams (const std::vector< Derived > &As)
     Gram-Schmidt orthogonalization.
template<typename Derived >
  dyn mat< typename Derived::Scalar > qpp::grams (const std::initializer list< Derived > &As)
     Gram-Schmidt orthogonalization.
• template<typename Derived >
  dyn mat< typename Derived::Scalar > qpp::grams (const Eigen::MatrixBase< Derived > &A)
     Gram-Schmidt orthogonalization.

    std::vector< idx > qpp::n2multiidx (idx n, const std::vector< idx > &dims)

     Non-negative integer index to multi-index.

    idx qpp::multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

     Multi-index to non-negative integer index.
```

ket qpp::mket (const std::vector< idx > &mask, const std::vector< idx > &dims)

Multi-partite qudit ket.

ket qpp::mket (const std::vector< idx > &mask, idx d=2)

Multi-partite qudit ket.

cmat qpp::mprj (const std::vector < idx > &mask, const std::vector < idx > &dims)

Projector onto multi-partite qudit ket.

cmat qpp::mprj (const std::vector< idx > &mask, idx d=2)

Projector onto multi-partite qudit ket.

template<typename InputIterator >

```
std::vector< double > qpp::abssq (InputIterator first, InputIterator last)
```

Computes the absolute values squared of an STL-like range of complex numbers.

• template<typename Container >

```
std::vector< double > qpp::abssq (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)
```

Computes the absolute values squared of an STL-like container.

template<typename Derived >

```
std::vector< double > qpp::abssq (const Eigen::MatrixBase< Derived > &A)
```

Computes the absolute values squared of an Eigen expression.

• template<typename InputIterator >

```
std::iterator_traits< InputIterator >::value_type qpp::sum (InputIterator first, InputIterator last)
```

Element-wise sum of an STL-like range.

template<typename Container >

```
Container::value_type qpp::sum (const Container &c, typename std::enable_if< is_iterable< Container >
::value >::type *=nullptr)
```

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

```
std::iterator_traits< InputIterator >::value_type qpp::prod (InputIterator first, InputIterator last)
```

Element-wise product of an STL-like range.

template<typename Container >

```
Container::value_type qpp::prod (const Container &c, typename std::enable_if< is_iterable< Container >
::value >::type *=nullptr)
```

Element-wise product of the elements of an STL-like container.

• template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > qpp::rho2pure (const Eigen::MatrixBase< Derived > &A)
```

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

• std::vector< idx > qpp::complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

```
std::vector< double > qpp::rho2bloch (const Eigen::MatrixBase< Derived > &A)
```

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat qpp::bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

template<char... Bits>

```
ket qpp::literals::operator"" _ket ()
```

Multi-partite qubit ket user-defined literal.

• template<char... Bits>

```
bra qpp::literals::operator"" _bra ()
```

Multi-partite qubit bra user-defined literal.

• template<char... Bits>

```
cmat qpp::literals::operator"" _prj ()
```

Multi-partite qubit projector user-defined literal.


8.16.1 Detailed Description

Generic quantum computing functions.

8.17 input output.h File Reference

Input/output functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 internal::IOManipEigen qpp::disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
 Eigen expression ostream manipulator.

internal::IOManipEigen qpp::disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

• template<typename InputIterator >

internal::IOManipRange< InputIterator > qpp::disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")

Range ostream manipulator.

• template<typename Container >

internal::IOManipRange< typename Container::const_iterator > qpp::disp (const Container &c, const std⇔ ::string &separator, const std::string &start="[", const std::string &end="]", typename std::enable_if< is_⇔ iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

• template<typename PointerType >

internal::IOManipPointer< PointerType > qpp::disp (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")

C-style pointer ostream manipulator.

• template<typename Derived >

void qpp::save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.


8.17.1 Detailed Description

Input/output functions.

8.18 instruments.h File Reference

Measurement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)
 Generalized inner product.

template<typename Derived >

 $\label{lem:dyn_col_vect} $$ dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2) $$$

Generalized inner product.

ullet template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >
 std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase
 Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template < typename Derived >

 $std::tuple < idx, std::vector < double >, std::vector < cmat > > qpp::measure (const Eigen::MatrixBase < Derived > &A, const std::initializer_list < cmat > &Ks, const std::vector < idx > &target, const std::vector < idx > &dims)$

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > qpp::measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > qpp::measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, idx d=2)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.


8.18.1 Detailed Description

Measurement functions.

8.19 internal/classes/iomanip.h File Reference

Input/output manipulators.

This graph shows which files directly or indirectly include this file:



Classes

- class qpp::internal::IOManipRange< InputIterator >
- class qpp::internal::IOManipPointer< PointerType >
- class qpp::internal::IOManipEigen

Namespaces

- qpp
 - Quantum++ main namespace.
- qpp::internal

Internal utility functions, do not use them directly or modify them.


8.19.1 Detailed Description

Input/output manipulators.

8.20 internal/classes/singleton.h File Reference

Singleton pattern via CRTP.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::internal::Singleton< T >

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Namespaces

• qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


8.20.1 Detailed Description

Singleton pattern via CRTP.

8.21 internal/util.h File Reference

Internal utility functions.

This graph shows which files directly or indirectly include this file:



Classes

struct qpp::internal::Display_Impl_

Namespaces

qpp

Quantum++ main namespace.

· qpp::internal

Internal utility functions, do not use them directly or modify them.

Functions

- void qpp::internal::n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx qpp::internal::multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- $\bullet \ \ {\it template}{<} {\it typename Derived} >$

bool qpp::internal::check square mat (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

bool qpp::internal::check_vector (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_rvector (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_cvector (const Eigen::MatrixBase< Derived > &A)

• template<typename T >

bool qpp::internal::check nonzero size (const T &x) noexcept

• template<typename T1 , typename T2 >

bool qpp::internal::check_matching_sizes (const T1 &lhs, const T2 &rhs) noexcept

- bool qpp::internal::check dims (const std::vector < idx > &dims)
- template<typename Derived >

bool qpp::internal::check_dims_match_mat (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_dims_match_cvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_dims_match_rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- bool qpp::internal::check eq dims (const std::vector < idx > &dims, idx dim) noexcept
- bool app::internal::check no duplicates (std::vector< idx > v)
- bool qpp::internal::check_subsys_match_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)
- $\bullet \ \ {\it template}{<} {\it typename Derived} >$

bool qpp::internal::check_qubit_matrix (const Eigen::MatrixBase< Derived > &A) noexcept

• template<typename Derived >

bool qpp::internal::check_qubit_cvector (const Eigen::MatrixBase< Derived > &A) noexcept

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

 $bool\ qpp::internal::check_qubit_rvector\ (const\ Eigen::MatrixBase < Derived > \&A)\ noexcept$

• template<typename Derived >

bool qpp::internal::check_qubit_vector (const Eigen::MatrixBase< Derived > &A) noexcept

- bool qpp::internal::check_perm (const std::vector< idx > &perm)
- template<typename Derived1 , typename Derived2 >

 $dyn_mat < typename Derived1::Scalar > qpp::internal::kron2 (const Eigen::MatrixBase < Derived1 > &A, const Eigen::MatrixBase < Derived2 > &B)$

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::internal::dirsum2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::MatrixBase< Derived2 > &B)

• template<typename T >

void qpp::internal::variadic_vector_emplace (std::vector< T > &)

- template<typename T , typename First , typename... Args>
 - void qpp::internal::variadic_vector_emplace (std::vector< T > &v, First &&first, Args &&... args)
- idx qpp::internal::get_num_subsys (idx D, idx d)
- idx qpp::internal::get_dim_subsys (idx sz, idx N)

8.21.1 Detailed Description

Internal utility functions.

8.22 MATLAB/matlab.h File Reference

Input/output interfacing with MATLAB.

```
#include "mat.h"
#include "mex.h"
```

Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< cplx > ::type
 qpp::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::

Scalar > >::type qpp::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >
 std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.


8.22.1 Detailed Description

Input/output interfacing with MATLAB.

8.23 number_theory.h File Reference

Number theory functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

std::vector< int > qpp::x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double qpp::contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

• bigint qpp::gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint qpp::gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint qpp::lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint qpp::lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > qpp::invperm (const std::vector< idx > &perm)

Inverse permutation.

 $\bullet \; \mathsf{std} :: \mathsf{vector} < \mathsf{idx} > \mathsf{qpp} :: \mathsf{compperm} \; (\mathsf{const} \; \mathsf{std} :: \mathsf{vector} < \mathsf{idx} > \& \mathsf{perm}, \; \mathsf{const} \; \mathsf{std} :: \mathsf{vector} < \mathsf{idx} > \& \mathsf{sigma}) \\$

Compose permutations.

std::vector< bigint > qpp::factors (bigint a)

Prime factor decomposition.

• bigint qpp::modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

• bigint qpp::modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

• std::tuple< bigint, bigint, bigint > qpp::egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint qpp::modinv (bigint a, bigint p)

Modular inverse of a mod p.

• bool qpp::isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

• bigint qpp::randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

- std::vector< std::pair< int, int > > qpp::convergents (const std::vector< int > &cf)
 Convergents.
- std::vector< std::pair< int, int > > qpp::convergents (double x, idx N)
 Convergents.


8.23.1 Detailed Description

Number theory functions.

8.24 operations.h File Reference

Quantum operation functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 const std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 idx d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

• template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std \leftrightarrow ::vector< idx > &target, const std::vector< idx > &dims)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std
::vector< idx > &target, idx d=2)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat qpp::kraus2super (const std::vector< cmat > &Ks)

Superoperator matrix.

cmat qpp::kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector< cmat > qpp::choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat qpp::choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat qpp::super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

dyn_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

template<typename Derived >

 $\label{lem:dyn_mat} $$ dyn_mat< typename\ Derived::Scalar > qpp::ptrace2\ (const\ Eigen::MatrixBase<\ Derived > \&A,\ const\ std $$::vector< idx > \&dims)$$

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Partial transpose.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2)

Partial transpose.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &perm, const std::vector< idx > &dims)

Subsystem permutation.

template<typename Derived >

 $\label{lem:dyn_mat} $$ dyn_mat< typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &perm, idx d=2)$

Subsystem permutation.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::applyQFT (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::applyTFQ (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > qpp::TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

• template<typename Derived >

 $dyn_col_vect< typename Derived::Scalar > qpp::QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)$

Qudit quantum Fourier transform.

8.24.1 Detailed Description

Quantum operation functions.

8.25 qpp.h File Reference

Quantum++ main header file, includes all other necessary headers.

```
#include <algorithm>
#include <cassert>
#include <chrono>
#include <cmath>
#include <complex>
#include <cstdlib>
#include <cstring>
#include <exception>
#include <fstream>
```

```
#include <functional>
#include <initializer_list>
#include <iomanip>
#include <iterator>
#include <limits>
#include <memory>
#include <numeric>
#include <ostream>
#include <random>
#include <sstream>
#include <stdexcept>
#include <string>
#include <tuple>
#include <type_traits>
#include <utility>
#include <vector>
#include <Eigen/Dense>
#include <Eigen/SVD>
#include "types.h"
#include "classes/exception.h"
#include "constants.h"
#include "traits.h"
#include "classes/idisplay.h"
#include "internal/util.h"
#include "internal/classes/iomanip.h"
#include "input_output.h"
#include "internal/classes/singleton.h"
#include "classes/random_devices.h"
#include "random.h"
#include "number_theory.h"
#include "functions.h"
#include "classes/init.h"
#include "classes/codes.h"
#include "classes/gates.h"
#include "classes/states.h"
#include "statistics.h"
#include "operations.h"
#include "entropies.h"
#include "entanglement.h"
#include "classes/timer.h"
#include "instruments.h"
#include "classes/reversible.h"
#include "classes/noise.h"
#include "classes/circuits.h"
```

Namespaces

dbb

Quantum++ main namespace.

Macros

#define QPP_UNUSED_

8.25.1 Detailed Description

Quantum++ main header file, includes all other necessary headers.

8.25.2 Macro Definition Documentation


8.25.2.1 QPP_UNUSED_

#define QPP_UNUSED_

8.26 random.h File Reference

Randomness-related functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

double qpp::rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

bigint qpp::rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx qpp::randidx (idx a=std::numeric_limits < idx >::min(), idx b=std::numeric_limits < idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

template<typename Derived >

Derived qpp::rand (idx rows, idx cols, double a=0, double b=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

template<>

dmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

template<>

cmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived qpp::randn (idx rows, idx cols, double mean=0, double sigma=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

• template<>

dmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

template<>

cmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

• double qpp::randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

cmat qpp::randU (idx D=2)

Generates a random unitary matrix.

cmat qpp::randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > qpp::randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat qpp::randH (idx D=2)

Generates a random Hermitian matrix.

ket qpp::randket (idx D=2)

Generates a random normalized ket (pure state vector)

cmat qpp::randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > qpp::randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > qpp::randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.


8.26.1 Detailed Description

Randomness-related functions.

8.27 statistics.h File Reference

Statistics functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

std::vector< double > qpp::uniform (idx N)

Uniform probability distribution vector.

std::vector< double > qpp::marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > qpp::marginalY (const dmat &probXY)

Marginal distribution.

• template<typename Container >

double qpp::avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_← iterable< Container >::value >::type *=nullptr)

Average.

• template<typename Container >

double qpp::cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Covariance.

 $\bullet \ \ \text{template}{<} \text{typename Container} >$

double qpp::var (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_← iterable< Container >::value >::type *=nullptr)

Variance.

• template<typename Container >

double qpp::sigma (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_← iterable< Container >::value >::type *=nullptr)

Standard deviation.

• template<typename Container >

 $\label{local-container} \begin{tabular}{ll} double & qpp::cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if < is_iterable < Container >::value >::type *=nullptr) \end{tabular}$

Correlation.

8.28 traits.h File Reference 387


8.27.1 Detailed Description

Statistics functions.

8.28 traits.h File Reference

Type traits.

This graph shows which files directly or indirectly include this file:



Classes

struct qpp::make_void< Ts >

Helper for qpp::to_void<> alias template.

struct qpp::is_iterable < T, typename >

Checks whether T is compatible with an STL-like iterable container.

- struct qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(*(std::declval < T >().end(
- struct qpp::is_matrix_expression< Derived >

Checks whether the type is an Eigen matrix expression.

struct qpp::is_complex< T >

Checks whether the type is a complex type.

struct qpp::is_complex< std::complex< T >>

Checks whether the type is a complex number type, specialization for complex types.

Namespaces

• qpp

Quantum++ main namespace.

Typedefs

```
    template < typename... Ts>
        using qpp::to_void = typename make_void < Ts... > ::type
        Alias template that implements the proposal for void_t.
```


8.28.1 Detailed Description

Type traits.

8.29 types.h File Reference

Type aliases.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Typedefs

```
using qpp::idx = std::size_t
```

Non-negative integer index, make sure you use an unsigned type.

- using qpp::bigint = long long int
 - Big integer.
- using qpp::cplx = std::complex < double >

Complex number in double precision.

using qpp::ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector.

• using qpp::bra = Eigen::RowVectorXcd

Complex (double precision) dynamic Eigen row vector.

• using qpp::cmat = Eigen::MatrixXcd

Complex (double precision) dynamic Eigen matrix.

using qpp::dmat = Eigen::MatrixXd

Real (double precision) dynamic Eigen matrix.

template<typename Scalar >

```
using \ \ qpp::dyn\_mat = Eigen::Matrix < Scalar, \ Eigen::Dynamic, \ Eigen::Dynamic > \\
```

Dynamic Eigen matrix over the field specified by Scalar.

• template<typename Scalar >

```
using qpp::dyn_col_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 >
```

Dynamic Eigen column vector over the field specified by Scalar.

 $\bullet \ \ \text{template}{<} \text{typename Scalar} >$

```
using qpp::dyn_row_vect = Eigen::Matrix< Scalar, 1, Eigen::Dynamic >
```

Dynamic Eigen row vector over the field specified by Scalar.

Type aliases.

8.30 /Users/vlad/qpp/README.md File Reference

Index

/Users/vlad/qpp/README.md, 389	avg
_to_JSON	qpp, 36
qpp::QCircuitDescription, 283	
~Codes	b00
qpp::Codes, 136	qpp::States, 329
~Dynamic_bitset	b01
qpp::Dynamic_bitset, 158	qpp::States, 330
~Gates	b10
qpp::Gates, 174	gpp::States, 330
	b11
~IDisplay	qpp::States, 330
qpp::IDisplay, 190	
~IQCircuit	begin
qpp::IQCircuit, 207	qpp::QCircuitDescription, 283
~Init	bigint
qpp::Init, 192	qpp, <mark>26</mark>
\sim NoiseBase	Bit_circuit
qpp::NoiseBase, 250	qpp::Bit_circuit, 131
~QCircuitDescription	bloch2rho
qpp::QCircuitDescription, 283	qpp, 36
~RandomDevices	bra
qpp::RandomDevices, 317	qpp, 26
	4pp, 20
~Singleton	c red
qpp::internal::Singleton, 321	c_reg_
~States	qpp::QCircuitDescription::MeasureStep, 243
qpp::States, 327	cCTRL_custom
\sim Timer	qpp::QCircuitDescription, 286
qpp::Timer, 338	cCTRL
	qpp::QCircuitDescription, 284, 285
A_	CNOTba
qpp::internal::IOManipEigen, 197	qpp::Gates, 183
absm	CNOT
qpp, 28	qpp::Bit_circuit, 131
abssq	qpp::Bit_circuit::Gate_count, 170
•	
qpp, 29	qpp::Gates, 183
adjoint	CTRL_custom
qpp, 30	qpp::QCircuitDescription, 289
all	CTRL
qpp::Dynamic_bitset, 158	qpp::Gates, 175
anticomm	qpp::QCircuitDescription, 287, 288
qpp, 30	cbegin
any	qpp::QCircuitDescription, 284
qpp::Dynamic_bitset, 158	cend
apply	qpp::QCircuitDescription, 286
qpp, 31–33	check_cvector
applyCTRL	qpp::internal, 120
qpp, 33, 34	check_dims
applyQFT	qpp::internal, 120
qpp, 35	check_dims_match_cvect
applyTFQ	qpp::internal, 120
app. 35	check dims match mat

qpp::internal, 121	compperm
check_dims_match_rvect	qpp, 38
qpp::internal, 121	compute_probs_
check_eq_dims	qpp::NoiseBase, 250
qpp::internal, 121	compute_state_
check_matching_sizes	qpp::NoiseBase, 250
qpp::internal, 121	concurrence
check_no_duplicates	qpp, 40
qpp::internal, 121	conjugate
check_nonzero_size	qpp, 40
qpp::internal, 121	const_iterator
check_perm	qpp::QCircuitDescription, 281
qpp::internal, 122	constants.h, 363
check_qubit_cvector	contfrac2x
qpp::internal, 122	qpp, 40
check_qubit_matrix	convergents
qpp::internal, 122	qpp, 41
check_qubit_rvector	cor
qpp::internal, 122	qpp, 42
check_qubit_vector	cosm
qpp::internal, 122	qpp, 42
check_rvector	count
qpp::internal, 122	qpp::Dynamic_bitset, 158
check_square_mat	COV
qpp::internal, 123	qpp, 43
check_subsys_match_dims	cplx
qpp::internal, 123	qpp, 27
check_vector	ctrl_
qpp::internal, 123	qpp::QCircuitDescription::GateStep, 187
choi2kraus	CustomException
qpp, 36	qpp::exception::CustomException, 138
choi2super	cwise
qpp, 37	qpp, 43 CZ
chop	qpp::Gates, 183
qpp, 116	qppdates, 100
chop_	d
qpp::internal::IOManipEigen, 197	qpp::NoiseBase, 253
classes/circuits.h, 353	gpp::QCircuitDescription, 300
classes/codes.h, 354	qpp::QuditDepolarizingNoise, 315
classes/exception.h, 355	data
classes/gates.h, 357	qpp::Dynamic_bitset, 158
classes/idisplay.h, 358	det
classes/init.h, 358	qpp, 44
classes/noise.h, 359	difference_type
classes/random_devices.h, 360	qpp::QCircuitDescription::iterator, 221
classes/reversible.h, 361	dirsum
classes/states.h, 361	qpp, 44–46
classes/timer.h, 362	dirsum2
cmat	qpp::internal, 123
qpp, 26	dirsumpow
Codes	qpp, 46
qpp::Codes, 136	disp
codeword	qpp, 47, 48
qpp::Codes, 136	display
comm	qpp::Dynamic_bitset, 159
qpp, 37	qpp::IDisplay, 190
complement	qpp::IQCircuit, 207
qpp, 38	qpp::QCircuitDescription, 289

qpp::QCircuitDescription::iterator::value_type_←	qpp::exception::MatrixNotCvector, 229
, 348	qpp::exception::MatrixNotRvector, 231
qpp::Timer, 338	qpp::exception::MatrixNotSquare, 233
qpp::internal::IOManipEigen, 197	qpp::exception::MatrixNotSquareNorCvector, 235
qpp::internal::IOManipPointer, 199	qpp::exception::MatrixNotSquareNorRvector, 237
qpp::internal::IOManipRange, 202	qpp::exception::MatrixNotSquareNorVector, 239
display_impl_	qpp::exception::MatrixNotVector, 241
qpp::internal::Display_Impl_, 152	qpp::exception::NoCodeword, 246
dits_	qpp::exception::NotBipartite, 256
qpp::IQCircuit, 213	qpp::exception::NotImplemented, 258
dmat	app::exception::NotQubitCvector, 260
qpp, 27	qpp::exception::NotQubitMatrix, 262
dyn_col_vect	app::exception::NotQubitRvector, 264
qpp, 27 dyn mat	<pre>qpp::exception::NotQubitSubsys, 266 qpp::exception::NotQubitVector, 268</pre>
qpp, 27	qpp::exception::OutOfRange, 270
dyn_row_vect	qpp::exception::PermInvalid, 272
qpp, 27	qpp::exception::PermMismatchDims, 274
Dynamic_bitset	qpp::exception::QuditAlreadyMeasured, 312
qpp::Bit_circuit, 132	qpp::exception::SizeMismatch, 323
qpp::Dynamic_bitset, 157	qpp::exception::SubsysMismatchDims, 335
qpp2}/!aio_5/!oot, 10/	qpp::exception::TypeMismatch, 342
ee	qpp::exception::UndefinedType, 344
qpp, 116	qpp::exception::Unknown, 346
egcd	qpp::exception::ZeroSize, 351
qpp, 49	expandout
eig	qpp::Gates, 175, 176
qpp, 49	experimental/experimental.h, 367
elem_	expm
qpp::QCircuitDescription::iterator, 224	qpp, 52
end	111-1-7-
qpp::QCircuitDescription, 289, 290	FRED
end_	qpp::Bit_circuit, 132
qpp::Timer, 340	qpp::Bit_circuit::Gate_count, 171
qpp::internal::IOManipPointer, 200	qpp::Gates, 183
qpp::internal::IOManipRange, 203	factors
entanglement	qpp, 53
qpp, 50	Fd
entanglement.h, 364	qpp::Gates, 177
entropies.h, 366	fill_Ks_
entropy	qpp::QuditDepolarizingNoise, 315
qpp, 51	fill_probs_
eps	qpp::QuditDepolarizingNoise, 315
qpp, 116	first_
evals	qpp::internal::IOManipRange, 203
qpp, 51	flip
evects	qpp::Dynamic_bitset, 159
qpp, 52 Exception	functions.h, 367
qpp::exception::DimsInvalid, 141	funm
qpp::exception::DimsMismatchCvector, 143	qpp, 53
qpp::exception::DimsMismatchMatrix, 145	GHZ
qpp::exception::DimsMismatchRvector, 147	qpp::States, 330
qpp::exception::DimsMismatchVector, 147 qpp::exception::DimsMismatchVector, 149	gate
qpp::exception::DimsNotEqual, 151	qpp::QCircuitDescription, 290, 291
qpp::exception::Duplicates, 154	gate_
qpp::exception::Exception, 169	qpp::QCircuitDescription::GateStep, 187
qpp::exception::InvalidIterator, 194	gate_count
qpp::exception::MatrixMismatchSubsys, 227	qpp::Bit_circuit, 134
Appo.ooptionviatii.viiioinatoiloaboyo, 227	4ppbit_0ii0dit, 101

gate custom	get measurement count
qpp::QCircuitDescription, 291	qpp::QCircuitDescription, 294
gate fan	get_measurement_steps
qpp::QCircuitDescription, 292	qpp::QCircuitDescription, 294
gate_type_	get measurements
gpp::QCircuitDescription::GateStep, 187	qpp::QCircuitDescription, 294
GateStep	get name
qpp::QCircuitDescription::GateStep, 186	qpp::Gates, 178
GateType	qpp::QCircuitDescription, 295
qpp::QCircuitDescription, 281	get nc
Gates	qpp::QCircuitDescription, 295
qpp::Gates, 174	get_non_measured
gates_	qpp::QCircuitDescription, 295
qpp::QCircuitDescription, 300	get_not_measured
	qpp::IQCircuit, 210
gcd	get nq
qpp, 54	qpp::QCircuitDescription, 295
gconcurrence	get_num_subsys
qpp, 54	qpp::internal, 123
generated_	get_prng
qpp::NoiseBase, 253	qpp::RandomDevices, 318
get	get_probs
qpp::Dynamic_bitset, 160	
get_Ks	qpp::IQCircuit, 210
qpp::NoiseBase, 251	qpp::NoiseBase, 252
get_circuit_description	get_psi
qpp::IQCircuit, 207	qpp::IQCircuit, 210
get_d	get_q_ip
qpp::NoiseBase, 251	qpp::IQCircuit, 210
qpp::QCircuitDescription, 293	get_ref_psi
get_dim_subsys	qpp::IQCircuit, 211
qpp::internal, 123	get_relative_pos_
get_dit	qpp::IQCircuit, 211
qpp::IQCircuit, 208	get_steps_count
get_dits	qpp::QCircuitDescription, 296
qpp::IQCircuit, 208	get_thread_local_instance
get_duration	qpp::internal::Singleton, 321
qpp::Timer, 339	grams
get_gate_count	qpp, 55, 56
qpp::QCircuitDescription, 293	
get_gates	H
qpp::QCircuitDescription, 293	qpp::Gates, 183
get_instance	heig
qpp::internal::Singleton, 321	qpp, 56
	hevals
get_ip qpp::IQCircuit, 208	qpp, 57
_ " '	hevects
get_iter	qpp, 57
qpp::IQCircuit, 208	
get_last_idx	i_
qpp::NoiseBase, 251	qpp::NoiseBase, 253
get_last_K	IDisplay
qpp::NoiseBase, 251	qpp::IDisplay, 189, 190
get_last_p	IOManipEigen
qpp::NoiseBase, 251	qpp::internal::IOManipEigen, 196
get_m_ip	IOManipPointer
qpp::IQCircuit, 209	qpp::internal::IOManipPointer, 199
get_measured	IOManipRange
qpp::IQCircuit, 209	qpp::internal::IOManipRange, 202
qpp::QCircuitDescription, 293, 294	IQCircuit

1001 11 000 007	
app::IQCircuit, 206, 207	qpp, 28
qpp::QCircuit, 276 qpp::QCircuitDescription::iterator, 224	kraus2choi
Id	qpp, 59 kraus2super
qpp::Gates, 178	qpp, 60
Id2	kron
qpp::Gates, 184	qpp, 60–62
idx	черь, 80–82 kron2
qpp, 28	qpp::internal, 124
idx_infty	kronpow
qpp, 116	qpp, 62
index	Ks
qpp::Dynamic_bitset, 160	qpp::NoiseBase, 253
infty	
qpp, 116	last_
Init	qpp::internal::IOManipRange, 203
qpp::Init, 192	lcm
input_output.h, 372	qpp, 63
instruments.h, 373	load
internal/classes/iomanip.h, 374	qpp, 64
internal/classes/singleton.h, 375	qpp::RandomDevices, 318
internal/util.h, 376	loadMATLAB
internal::Singleton < const Codes >	qpp, 64, 65
qpp::Codes, 137	logdet
internal::Singleton < const Gates >	qpp, 66 logm
qpp::Gates, 183	qpp, 66
internal::Singleton< const Init >	lognegativity
qpp::Init, 193 internal::Singleton < const States >	qpp, 67
qpp::States, 329	٩٣٢
internal::Singleton< RandomDevices >	m_ip_
qpp::RandomDevices, 319	qpp::QCircuitDescription::iterator::value_type_←
inverse	, 349
qpp, 57	MATLAB/matlab.h, 378
invperm	MODMUL
qpp, 58	qpp::Gates, 178
ip	marginalX
qpp, 58, 59	qpp, 67
ip_	marginalY
qpp::QCircuitDescription::iterator::value_type $_{\leftarrow}$	qpp, 69
, 349	mats_ qpp::QCircuitDescription::MeasureStep, 243
is_measurement_	maxn
qpp::QCircuitDescription::iterator::value_type_←	qpp, 116
, 349	measure
is_measurement_step	qpp, 69–74
qpp::IQCircuit, 211	measure_seq
isprime	qpp, 74, 75
qpp, 59	MeasureStep
rt_ qpp::IQCircuit, 213	qpp::QCircuitDescription::MeasureStep, 243
iterator	MeasureType
qpp::QCircuitDescription::iterator, 222	qpp::QCircuitDescription, 282
iterator_category	measured_
	qpp::QCircuitDescription, 300
qpp::QCircuitDescription::iterator, 221	qpp::QCircuitDescription, 300 measurement_steps_
	qpp::QCircuitDescription, 300
qpp::QCircuitDescription::iterator, 221	qpp::QCircuitDescription, 300 measurement_steps_ qpp::QCircuitDescription, 300 measurement_type_
<pre>qpp::QCircuitDescription::iterator, 221 jn</pre>	qpp::QCircuitDescription, 300 measurement_steps_ qpp::QCircuitDescription, 300 measurement_type_ qpp::QCircuitDescription::MeasureStep, 244
qpp::QCircuitDescription::iterator, 221 jn	qpp::QCircuitDescription, 300 measurement_steps_ qpp::QCircuitDescription, 300 measurement_type_

qpp::QCircuitDescription, 301	qpp, 82
measureV	one
qpp::QCircuitDescription, 296	qpp::States, 328
measureZ	operations.h, 380
qpp::QCircuitDescription, 297	operator!=
mes	qpp::Dynamic_bitset, 161
qpp::States, 327	qpp::QCircuitDescription::iterator, 222
minus	operator<<
qpp::States, 328	qpp::IDisplay, 191
mket	qpp::QCircuitDescription, 298, 299
qpp, 75, 76	operator*
modinv	qpp::QCircuitDescription::iterator, 222
qpp, 76	operator()
modmul	qpp::NoiseBase, 252
qpp, 77	operator++
modpow	qpp::QCircuitDescription::iterator, 222, 223
qpp, 77	operator-
mprj	qpp::Dynamic_bitset, 161
qpp, 78	operator=
msg_	qpp::IDisplay, 190
qpp::exception::Exception, 170	qpp::QCircuitDescription::iterator, 223
multiidx2n	qpp::QCircuitDescription::iterator::value_type_←
qpp, 79	, 349
qpp::internal, 124	qpp::Timer, 339
	qpp::internal::IOManipPointer, 199
n2multiidx	qpp::internal::IOManipRange, 202
qpp, 79	qpp::internal::Singleton, 321
qpp::internal, 124	operator==
N_	qpp::Dynamic_bitset, 162
qpp::Dynamic_bitset, 165	qpp::QCircuitDescription::iterator, 223
qpp::internal::IOManipPointer, 200	operator"" _bra
NOT	qpp::literals, 125
qpp::Bit_circuit, 132	operator"" _i
qpp::Bit_circuit::Gate_count, 171	qpp, 82
name_	qpp::literals, 125
qpp::QCircuitDescription, 301	operator"" _ket
qpp::QCircuitDescription::GateStep, 187	qpp::literals, 126
qpp::QCircuitDescription::MeasureStep, 244	operator"" _prj
nc_	qpp::literals, 126
qpp::QCircuitDescription, 301	
negativity	p_
qpp, 80	qpp::internal::IOManipPointer, 200
noise_type	pGHZ
qpp::NoiseBase, 248	qpp::States, 331
NoiseBase	pb00
qpp::NoiseBase, 249	qpp::States, 330
none	pb01
qpp::Dynamic_bitset, 160	qpp::States, 330
norm	pb10
qpp, 81	qpp::States, 331
normalize	pb11
qpp, 81	qpp::States, 331
nq_	pi
qpp::QCircuitDescription, 301	qpp, 117
number_theory.h, 378	plus
_	qpp::States, 328
offset_	pointer
qpp::Dynamic_bitset, 161	qpp::QCircuitDescription::iterator, 221
omega	powm

	qpp, 82	applyTFQ, 35
prj		avg, 36
	qpp, 83	bigint, 26
prng		bloch2rho, 36
88	qpp::RandomDevices, 319	bra, 26
prob		•
proc		choi2kraus, 36
	qpp::IQCircuit, 213	choi2super, 37
	qpp::NoiseBase, 254	chop, 116
proc		cmat, 26
	qpp, 83, 84	comm, 37
psi_		complement, 38
	qpp::IQCircuit, 213	compperm, 38
ptra	ce	concurrence, 40
•	qpp, 84, 85	conjugate, 40
ptra		
pua	qpp, 85, 86	contfrac2x, 40
ntro		convergents, 41
ptra		cor, 42
	qpp, 86, 87	cosm, 42
ptra	nspose	cov, 43
	qpp, 87, 88	cplx, 27
рW		cwise, 43
	qpp::States, 331	det, 44
px0		dirsum, 44–46
•	qpp::States, 331	
px1		dirsumpow, 46
PΛΙ	ann: States 221	disp, 47, 48
0	qpp::States, 331	dmat, 27
py0	0	dyn_col_vect, 27
	qpp::States, 332	dyn_mat, 27
py1		dyn_row_vect, 27
	qpp::States, 332	ee, 116
pz0		egcd, 49
	qpp::States, 332	-
pz1		eig, 49
•	qpp::States, 332	entanglement, 50
	4pp.:.e.ca.co.;	entropy, 51
q_ip		eps, 116
	_ qpp::QCircuitDescription::iterator::value_type_←	evals, 51
	, 349	evects, 52
OCi	rcuitDescription	expm, 52
QUII	•	factors, 53
	qpp::QCircuitDescription, 282	funm, 53
	qpp::QCircuitDescription::iterator, 224	
QFT		gcd, 54
	qpp, 88	gconcurrence, 54
	qpp::QCircuitDescription, 297	grams, 55, 56
QPF	P_UNUSED_	heig, <mark>56</mark>
	qpp.h, 384	hevals, 57
qcd		hevects, 57
-1	qpp::IQCircuit, 213	idx, 28
	qpp::QCircuitDescription::iterator, 224	idx_infty, 116
amı		infty, 116
qınu	tualinfo	inverse, 57
	qpp, 89	
qpp,		invperm, 58
	absm, 28	ip, 58, 59
	abssq, 29	isprime, 59
	adjoint, 30	ket, 28
	anticomm, 30	kraus2choi, 59
	apply, 31–33	kraus2super, 60
	applyCTRL, 33, 34	kron, 60–62
	applyQFT, 35	kronpow, 62
	appy st 1,00	MONPOW, UZ

lcm, 63	spectralpowm, 107
load, 64	sqrtm, 108
loadMATLAB, 64, 65	sum, 108, 109
logdet, 66	super2choi, 109
logm, 66	svals, 110
lognegativity, 67	svd, 110
marginalX, 67	svdU, 110
marginalY, 69	svdV, 111
maxn, 116	syspermute, 111, 112
measure, 69–74	TFQ, 112
measure_seq, 74, 75	to_void, 28
mket, 75, 76	trace, 112
modinv, 76	transpose, 113
modmul, 77	tsallis, 113, 114
modpow, 77	uniform, 114
mprj, 78	var, 115
multiidx2n, 79	x2contfrac, 115
n2multiidx, 79	qpp.h, 382
negativity, 80	QPP_UNUSED_, 384
norm, 81	qpp::Bit circuit, 129
normalize, 81	Bit_circuit, 131
omega, 82	CNOT, 131
operator"" _i, 82	Dynamic_bitset, 132
pi, 117	FRED, 132
powm, 82	gate count, 134
prj, 83	NOT, 132
prod, 83, 84	reset, 132
ptrace, 84, 85	SWAP, 133
ptrace1, 85, 86	TOF, 133
ptrace2, 86, 87	X, 133
ptranspose, 87, 88	qpp::Bit_circuit::Gate_count, 170
QFT, 88	CNOT, 170
qmutualinfo, 89	FRED, 171
rand, 90–92	NOT, 171
randH, 92	SWAP, 171
randidx, 93	TOF, 171
randket, 93	X, 171
randkraus, 93	qpp::Codes, 134
randn, 94, 95	~Codes, 136
randperm, 96	Codes, 136
randprime, 96	codeword, 136
randprob, 97	internal::Singleton< const Codes >, 137
randrho, 97	Type, 135
randU, 97	qpp::Dynamic bitset, 155
randV, 98	~Dynamic_bitset, 158
renyi, 98, 99	all, 158
reshape, 99	any, 158
rho2bloch, 100	count, 158
rho2pure, 100	data, 158
•	
save, 101	display, 159
saveMATLAB, 101, 102	Dynamic_bitset, 157
schatten, 102	flip, 159
schmidtA, 103	get, 160
schmidtB, 103, 104	index_, 160
schmidtcoeffs, 104, 105	N_, 165
schmidtprobs, 105, 106	none, 160
sigma, 106	offset_, 161
sinm, 107	operator!=, 161

operator-, 161	get_measured, 209
operator==, 162	get_not_measured, 210
rand, 162, 163	get_probs, 210
reset, 163	get_psi, <mark>210</mark>
set, 163, 164	get_q_ip, 210
size, 164	get_ref_psi, <mark>211</mark>
storage_size, 164	get_relative_pos_, 211
storage_size_, 165	IQCircuit, 206, 207
storage_type, 157	is_measurement_step, 211
to_string, 164	it_, 213
v_, 165	probs_, 213
value_type, 157	psi_, 213
qpp::Gates, 172	qcd_, 213
∼Gates, 174	reset, 211
CNOTba, 183	run, 212
CNOT, 183	set_dit, 212
CTRL, 175	set_measured_, 212
CZ, 183	subsys , 213
expandout, 175, 176	qpp::Init, 191
FRED, 183	∼Init, 192
Fd, 177	Init, 192
Gates, 174	
•	internal::Singleton< const Init >, 193
get_name, 178	qpp::NoiseBase
H, 183	~NoiseBase, 250
ld, 178	compute_probs_, 250
ld2, 184	compute_state_, 250
internal::Singleton< const Gates >, 183	d_, 253
MODMUL, 178	generated_, 253
Rn, 179	get_Ks, 251
RX, 179	get_d, 251
RY, 180	get_last_idx, 251
RZ, 180	get_last_K, <mark>251</mark>
S, 184	get_last_p, <mark>25</mark> 1
SWAPd, 180	get_probs, 252
SWAP, 184	i_, 253
T, 184	Ks_, 253
TOF, 184	noise_type, 248
X, 184	NoiseBase, 249
Xd, 182	operator(), 252
Y, 185	probs_, 254
Z, 185	qpp::NoiseBase< T >, 247
Zd, 182	qpp::NoiseType, 254
qpp::IDisplay, 188	qpp::NoiseType::StateDependent, 324
∼IDisplay, 190	qpp::NoiseType::StateIndependent, 324
display, 190	gpp::QCircuit, 275
IDisplay, 189, 190	IQCircuit, 276
operator<<, 191	run, 276
operator=, 190	qpp::QCircuitDescription, 277
qpp::IQCircuit, 204	to_JSON, 283
~IQCircuit, 207	~QCircuitDescription, 283
	•
display, 207	begin, 283
dits_, 213	cCTRL_custom, 286
get_circuit_description, 207	cCTRL, 284, 285
get_dit, 208	CTRL_custom, 289
get_dits, 208	CTRL, 287, 288
get_ip, 208	cbegin, 284
get_iter, 208	cend, 286
get_m_ip, 209	const_iterator, 281

d_, 300	operator*, 222
display, 289	operator++, 222, 223
end, 289, 290	operator=, 223
gate, 290, 291	operator==, 223
gate_custom, 291	pointer, 221
gate_fan, 292	QCircuitDescription, 224
GateType, 281	qcd_, 224
gates_, 300	reference, 221
get_d, 293	set_, 224
get_gate_count, 293	value_type, 221
get_gates, 293	qpp::QCircuitDescription::iterator::value_type_, 347
get_measured, 293, 294	display, 348
get_measurement_count, 294	ip_, 349
get_measurement_steps, 294	is_measurement_, 349
get_measurements, 294	 m_ip_, 349
get_name, 295	operator=, 349
get_nc, 295	q_ip_, 349
get_non_measured, 295	value_type_, 348
get_nq, 295	value_type_qcd_, 350
get_steps_count, 296	qpp::QubitAmplitudeDampingNoise, 302
MeasureType, 282	QubitAmplitudeDampingNoise, 303
measured_, 300	qpp::QubitBitFlipNoise, 303
measurement_steps_, 300	QubitBitFlipNoise, 304
measurements_, 301	qpp::QubitBitPhaseFlipNoise, 305
measureV, 296	QubitBitPhaseFlipNoise, 306
measureZ, 297	qpp::QubitDepolarizingNoise, 306
name_, 301	QubitDepolarizingNoise, 307
	qpp::QubitPhaseDampingNoise, 308
nc_, 301	QubitPhaseDampingNoise, 309
nq_, 301	qpp::QubitPhaseFlipNoise, 309
operator <<, 298, 299	QubitPhaseFlipNoise, 310
QCircuitDescription, 282	qpp::QuditDepolarizingNoise, 313
QFT, 297	
steps_cnt_, 301	d_, 315
TFQ, 298	fill_Ks_, 315
to_JSON, 298	fill_probs_, 315
qpp::QCircuitDescription::GateStep, 185	QuditDepolarizingNoise, 314
ctrl_, 187	qpp::RandomDevices, 316
gate_, 187	~RandomDevices, 317
gate_type_, 187	get_prng, 318
GateStep, 186	internal::Singleton< RandomDevices >, 319
name_, 187	load, 318
step_no_, 187	prng_, 319
target_, 188	RandomDevices, 317
qpp::QCircuitDescription::MeasureStep, 242	rd_, 319
c_reg_, 243	save, 318
mats_, 243	qpp::States, 324
MeasureStep, 243	\sim States, 327
measurement_type_, 244	b00, 329
name_, 244	b01, 330
step_no_, 244	b10, 330
target_, 244	b11, 330
qpp::QCircuitDescription::iterator, 219	GHZ, 330
difference_type, 221	internal::Singleton< const States >, 329
elem_, 224	jn, <mark>327</mark>
IQCircuit, 224	mes, 327
iterator, 222	minus, 328
iterator_category, 221	one, 328
operator!=, 222	pGHZ, 331

pb00, 330	type_description, 154
pb01, 330	qpp::exception::Exception, 166
pb10, 331	Exception, 169
pb11, 331	msg_, 170
plus, 328	type_description, 169
pW, 331	what, 169
px0, 331	where_, 170
px1, 331	qpp::exception::InvalidIterator, 193
py0, 332	Exception, 194
py1, 332	type_description, 195
pz0, 332	qpp::exception::MatrixMismatchSubsys, 226
pz1, 332	Exception, 227
States, 327	type_description, 227
W, 332	qpp::exception::MatrixNotCvector, 228
x0, <mark>332</mark>	Exception, 229
x1, 333	type_description, 229
y0, 333	qpp::exception::MatrixNotRvector, 230
y1, 333	Exception, 231
z0, 333	type_description, 231
z1, 333	qpp::exception::MatrixNotSquare, 232
zero, 329	Exception, 233
qpp::Timer	type description, 233
∼Timer, 338	qpp::exception::MatrixNotSquareNorCvector, 234
display, 338	Exception, 235
end_, 340	type_description, 235
get_duration, 339	qpp::exception::MatrixNotSquareNorRvector, 236
operator=, 339	Exception, 237
start_, 340	type_description, 237
tic, 339	qpp::exception::MatrixNotSquareNorVector, 238
tics, 340	Exception, 239
	•
Timer, 337, 338	type_description, 239
toc, 340	qpp::exception::MatrixNotVector, 240
qpp::Timer< T, CLOCK_T >, 336	Exception, 241
qpp::exception, 117	type_description, 241
qpp::exception::CustomException, 137	qpp::exception::NoCodeword, 245
CustomException, 138	Exception, 246
type_description, 139	type_description, 246
what_, 139	qpp::exception::NotBipartite, 255
qpp::exception::DimsInvalid, 140	Exception, 256
Exception, 141	type_description, 256
type_description, 141	qpp::exception::NotImplemented, 257
qpp::exception::DimsMismatchCvector, 142	Exception, 258
Exception, 143	type_description, 258
type_description, 143	qpp::exception::NotQubitCvector, 259
qpp::exception::DimsMismatchMatrix, 144	Exception, 260
Exception, 145	type_description, 260
type_description, 145	qpp::exception::NotQubitMatrix, 261
qpp::exception::DimsMismatchRvector, 146	Exception, 262
Exception, 147	type_description, 262
type_description, 147	qpp::exception::NotQubitRvector, 263
qpp::exception::DimsMismatchVector, 148	Exception, 264
Exception, 149	type_description, 264
type_description, 149	qpp::exception::NotQubitSubsys, 265
qpp::exception::DimsNotEqual, 150	Exception, 266
Exception, 151	type_description, 266
type_description, 151	qpp::exception::NotQubitVector, 267
qpp::exception::Duplicates, 153	Exception, 268
Exception, 154	type_description, 268

qpp::exception::OutOfRange, 269	display_impl_, 152
Exception, 270	qpp::internal::IOManipEigen, 195
type_description, 270	A_, 197
qpp::exception::PermInvalid, 271	chop_, 197
Exception, 272	display, 197
type_description, 272	IOManipEigen, 196
qpp::exception::PermMismatchDims, 273	qpp::internal::IOManipPointer
Exception, 274	display, 199
type_description, 274	end_, 200
qpp::exception::QuditAlreadyMeasured, 311	IOManipPointer, 199
Exception, 312	N_, 200
type_description, 313	operator=, 199
qpp::exception::SizeMismatch, 322	p_, 200
Exception, 323	separator_, 200
type_description, 323	start_, 200
qpp::exception::SubsysMismatchDims, 334	qpp::internal::IOManipPointer< PointerType >, 198
Exception, 335	qpp::internal::IOManipRange
type_description, 335	display, 202
qpp::exception::TypeMismatch, 341	end_, 203
Exception, 342	first_, 203
type_description, 343	IOManipRange, 202
qpp::exception::UndefinedType, 343	last_, 203
Exception, 344	operator=, 202
type_description, 345	separator_, 203
qpp::exception::Unknown, 345	start_, 203
Exception, 346	qpp::internal::IOManipRange< InputIterator >, 201
type_description, 347	qpp::internal::Singleton
qpp::exception::ZeroSize, 350	∼Singleton, 321
Exception, 351	get_instance, 321
type_description, 352	get_thread_local_instance, 321
qpp::experimental, 119	operator=, 321
qpp::internal, 119	Singleton, 320, 321
check_cvector, 120	qpp::internal::Singleton< T >, 319
check dims, 120	qpp::is_complex< std::complex< T >>, 215
check_dims_match_cvect, 120	qpp::is_complex< $T >$, 214
check_dims_match_mat, 121	qpp::is_iterable< T, to_void< decltype(std::declval< T
check_dims_match_rvect, 121	$>$ ().begin()), decltype(std::declval< T $>$ (). \leftrightarrow
check_eq_dims, 121	end()), decltype(*(std::declval $<$ T $>$ (). \leftarrow
check matching sizes, 121	begin()))>>, 217
check_no_duplicates, 121	qpp::is_iterable< T, typename >, 216
check nonzero size, 121	qpp::is_matrix_expression< Derived >, 218
check_perm, 122	qpp::literals, 125
check_qubit_cvector, 122	operator""_bra, 125
check_qubit_matrix, 122	operator"" _i, 125
check qubit rvector, 122	operator"" _ket, 126
check_qubit_vector, 122	operator"" _prj, 126
check_rvector, 122	qpp::make_void
check_square_mat, 123	type, 225
check_subsys_match_dims, 123	qpp::make_void $<$ Ts $>$, 225
check vector, 123	QubitAmplitudeDampingNoise
dirsum2, 123	qpp::QubitAmplitudeDampingNoise, 303
get_dim_subsys, 123	QubitBitFlipNoise
get_num_subsys, 123	qpp::QubitBitFlipNoise, 304
kron2, 124	QubitBitPhaseFlipNoise
multiidx2n, 124	qpp::QubitBitPhaseFlipNoise, 306
n2multiidx, 124	QubitDepolarizingNoise
variadic_vector_emplace, 124	qpp::QubitDepolarizingNoise, 307
qpp::internal::Display_Impl_, 152	QubitPhaseDampingNoise
appternalbispiay_impi_, 132	aunii nasebampingivoise

qpp::QubitPhaseDampingNoise, 309	RZ
	_
QubitPhaseFlipNoise	qpp::Gates, 180
qpp::QubitPhaseFlipNoise, 310	S
QuditDepolarizingNoise	qpp::Gates, 184
qpp::QuditDepolarizingNoise, 314	SWAPd
rand	qpp::Gates, 180
	SWAP
qpp, 90–92	_
qpp::Dynamic_bitset, 162, 163	qpp::Bit_circuit, 133
randH	qpp::Bit_circuit::Gate_count, 171
qpp, 92	qpp::Gates, 184
randidx	save
qpp, 93	qpp, 101
randket	qpp::RandomDevices, 318
qpp, 93	saveMATLAB
randkraus	qpp, 101, 102
qpp, 93	schatten
randn	qpp, 102
qpp, 94, 95	schmidtA
random.h, 384	qpp, 103
RandomDevices	schmidtB
qpp::RandomDevices, 317	qpp, 103, 104
randperm	schmidtcoeffs
·	qpp, 104, 105
qpp, 96	
randprime	schmidtprobs
qpp, 96	qpp, 105, 106
randprob	separator_
qpp, 97	qpp::internal::IOManipPointer, 200
randrho	qpp::internal::IOManipRange, 203
qpp, 9 7	set
randU	qpp::Dynamic_bitset, 163, 164
0.7	aat
qpp, 97	set_
qpp, 97 randV	qpp::QCircuitDescription::iterator, 224
	_
randV	qpp::QCircuitDescription::iterator, 224
randV qpp, 98	qpp::QCircuitDescription::iterator, 224 set_dit
randV qpp, 98 rd_	<pre></pre>
randV qpp, 98 rd_ qpp::RandomDevices, 319 reference	qpp::QCircuitDescription::iterator, 224 set_dit
randV	app::QCircuitDescription::iterator, 224 set_dit app::IQCircuit, 212 set_measured_ app::IQCircuit, 212 sigma app, 106 Singleton app::internal::Singleton, 320, 321 sinm app, 107 size
randV	qpp::QCircuitDescription::iterator, 224 set_dit

steps_cnt_	qpp::Codes, 135
qpp::QCircuitDescription, 301	type
storage_size	qpp::make_void, 225
qpp::Dynamic_bitset, 164	type_description
storage_size_	qpp::exception::CustomException, 139
qpp::Dynamic_bitset, 165	qpp::exception::DimsInvalid, 141
storage_type	qpp::exception::DimsMismatchCvector, 143
qpp::Dynamic_bitset, 157	qpp::exception::DimsMismatchMatrix, 145
	qpp::exception::DimsMismatchRvector, 147
subsys_	qpp::exception::DimsMismatchVector, 149
qpp::IQCircuit, 213	
sum	qpp::exception::DimsNotEqual, 151
qpp, 108, 109	qpp::exception::Duplicates, 154
super2choi	qpp::exception::Exception, 169
qpp, 109	qpp::exception::InvalidIterator, 195
svals	qpp::exception::MatrixMismatchSubsys, 227
qpp, 110	qpp::exception::MatrixNotCvector, 229
svd	qpp::exception::MatrixNotRvector, 231
qpp, 110	qpp::exception::MatrixNotSquare, 233
svdU	qpp::exception::MatrixNotSquareNorCvector, 235
qpp, 110	qpp::exception::MatrixNotSquareNorRvector, 237
svdV	qpp::exception::MatrixNotSquareNorVector, 239
qpp, 111	qpp::exception::MatrixNotVector, 241
syspermute	qpp::exception::NoCodeword, 246
qpp, 111, 112	qpp::exception::NotBipartite, 256
Т	qpp::exception::NotImplemented, 258
qpp::Gates, 184	qpp::exception::NotQubitCvector, 260
TFQ	qpp::exception::NotQubitMatrix, 262
	qpp::exception::NotQubitRvector, 264
qpp, 112	qpp::exception::NotQubitSubsys, 266
qpp::QCircuitDescription, 298	qpp::exception::NotQubitVector, 268
TOF	qpp::exception::OutOfRange, 270
qpp::Bit_circuit, 133	qpp::exception::PermInvalid, 272
qpp::Bit_circuit::Gate_count, 171	qpp::exception::PermMismatchDims, 274
qpp::Gates, 184	qpp::exception::QuditAlreadyMeasured, 313
target_	qpp::exception::SizeMismatch, 323
qpp::QCircuitDescription::GateStep, 188	qpp::exception::SubsysMismatchDims, 335
qpp::QCircuitDescription::MeasureStep, 244	qpp::exception::TypeMismatch, 343
tic	
qpp::Timer, 339	qpp::exception::UndefinedType, 345
tics	qpp::exception::Unknown, 347
qpp::Timer, 340	qpp::exception::ZeroSize, 352
Timer	types.h, 388
	,,
qpp::Timer, 337, 338	uniform
to_JSON	qpp, 114
qpp::QCircuitDescription, 298	
to_string	v_
qpp::Dynamic_bitset, 164	qpp::Dynamic_bitset, 165
to_void	value_type
qpp, 28	qpp::Dynamic_bitset, 157
toc	qpp::QCircuitDescription::iterator, 221
qpp::Timer, 340	value_type_
trace	qpp::QCircuitDescription::iterator::value_type_←
qpp, 112	, 348
traits.h, 387	value_type_qcd_
	qpp::QCircuitDescription::iterator::value_type_←
transpose	
qpp, 113	, 350
tsallis	var
qpp, 113, 114	qpp, 115
Туре	variadic_vector_emplace

```
qpp::internal, 124
W
    qpp::States, 332
what
    qpp::exception::Exception, 169
what_
    qpp::exception::CustomException, 139
where
    qpp::exception::Exception, 170
Χ
    qpp::Bit_circuit, 133
    qpp::Bit_circuit::Gate_count, 171
    qpp::Gates, 184
x0
    qpp::States, 332
х1
    qpp::States, 333
x2contfrac
    qpp, 115
Xd
    qpp::Gates, 182
Υ
    qpp::Gates, 185
y0
    qpp::States, 333
у1
    qpp::States, 333
Ζ
    qpp::Gates, 185
z0
    qpp::States, 333
z1
    qpp::States, 333
Zd
    qpp::Gates, 182
zero
    qpp::States, 329
```