Quantum++ v1.3

Generated by Doxygen 1.8.15

1 Quantum++	1
2 Namespace Index	3
2.1 Namespace List	3
3 Hierarchical Index	5
3.1 Class Hierarchy	5
4 Class Index	9
4.1 Class List	9
5 File Index	13
5.1 File List	13
6 Namespace Documentation	15
6.1 qpp Namespace Reference	15
6.1.1 Detailed Description	28
6.1.2 Typedef Documentation	28
6.1.2.1 bigint	29
6.1.2.2 bra	29
6.1.2.3 cmat	29
6.1.2.4 cplx	29
	29
	29
	30
, -	30
6.1.2.9 idx	30
	30
6.1.2.11 to void	30
<i>*</i>	30
•	30
	31
v	31
W. F. C.	31
W	32
6.1.4.4 abssq() [3/3]	32
6.1.4.5 adjoint()	32
6.1.4.6 anticomm()	33
6.1.4.7 apply() [1/5]	33
6.1.4.8 apply() [2/5]	34
6.1.4.9 apply() [3/5]	34
6.1.4.10 apply() [4/5]	35
6.1.4.11 apply() [5/5]	35
6.1.4.12 applyCTRL() [1/2]	36

6.1.4.13 applyCTRL() [2/2]
6.1.4.14 applyQFT()
6.1.4.15 applyTFQ()
6.1.4.16 avg()
6.1.4.17 bloch2rho()
6.1.4.18 choi2kraus()
6.1.4.19 choi2super()
6.1.4.20 comm()
6.1.4.21 complement()
6.1.4.22 compperm()
6.1.4.23 concurrence()
6.1.4.24 conjugate()
6.1.4.25 contfrac2x()
6.1.4.26 convergents() [1/2]
6.1.4.27 convergents() [2/2]
6.1.4.28 cor()
6.1.4.29 cosm()
6.1.4.30 cov()
6.1.4.31 cwise()
6.1.4.32 det()
6.1.4.33 dirsum() [1/4]
6.1.4.34 dirsum() [2/4]
6.1.4.35 dirsum() [3/4]
6.1.4.36 dirsum() [4/4]
6.1.4.37 dirsumpow()
6.1.4.38 disp() [1/5]
6.1.4.39 disp() [2/5]
6.1.4.40 disp() [3/5]
6.1.4.41 disp() [4/5]
6.1.4.42 disp() [5/5]
6.1.4.43 egcd()
6.1.4.44 eig()
6.1.4.45 entanglement() [1/2]
6.1.4.46 entanglement() [2/2] 52
6.1.4.47 entropy() [1/2]
6.1.4.48 entropy() [2/2]
6.1.4.49 evals()
6.1.4.50 evects()
6.1.4.51 expm()
6.1.4.52 factors()
6.1.4.53 funm()
6.1.4.54 gcd() [1/2]

6.1.4.55 gcd() [2/2]	55
6.1.4.56 gconcurrence()	56
6.1.4.57 grams() [1/3]	56
6.1.4.58 grams() [2/3]	57
6.1.4.59 grams() [3/3]	57
6.1.4.60 hash_eigen()	58
6.1.4.61 heig()	58
6.1.4.62 hevals()	59
6.1.4.63 hevects()	59
6.1.4.64 inverse()	59
6.1.4.65 invperm()	60
6.1.4.66 ip() [1/2]	60
6.1.4.67 ip() [2/2]	61
6.1.4.68 isprime()	61
6.1.4.69 kraus2choi()	61
6.1.4.70 kraus2super()	62
6.1.4.71 kron() [1/4]	62
6.1.4.72 kron() [2/4]	64
6.1.4.73 kron() [3/4]	64
6.1.4.74 kron() [4/4]	65
6.1.4.75 kronpow()	65
6.1.4.76 lcm() [1/2]	66
6.1.4.77 lcm() [2/2]	66
6.1.4.78 load()	67
6.1.4.79 loadMATLAB() [1/2]	67
6.1.4.80 loadMATLAB() [2/2]	68
6.1.4.81 logdet()	69
6.1.4.82 logm()	69
6.1.4.83 lognegativity() [1/2]	69
6.1.4.84 lognegativity() [2/2]	70
6.1.4.85 marginalX()	70
6.1.4.86 marginalY()	70
6.1.4.87 measure() [1/9]	71
6.1.4.88 measure() [2/9]	71
6.1.4.89 measure() [3/9]	72
6.1.4.90 measure() [4/9]	72
6.1.4.91 measure() [5/9]	73
6.1.4.92 measure() [6/9]	74
6.1.4.93 measure() [7/9]	74
6.1.4.94 measure() [8/9]	75
6.1.4.95 measure() [9/9]	76
6.1.4.96 measure_seq() [1/2]	76

6.1.4.97 measure_seq() [2/2]
6.1.4.98 mket() [1/2]
6.1.4.99 mket() [2/2]
6.1.4.100 modinv()
6.1.4.101 modmul()
6.1.4.102 modpow()
6.1.4.103 mprj() [1/2]
6.1.4.104 mprj() [2/2]
6.1.4.105 multiidx2n()
6.1.4.106 n2multiidx()
6.1.4.107 negativity() [1/2]
6.1.4.108 negativity() [2/2]
6.1.4.109 norm()
6.1.4.110 normalize()
6.1.4.111 omega()
6.1.4.112 powm()
6.1.4.113 prj()
6.1.4.114 prod() [1/3]
6.1.4.115 prod() [2/3]
6.1.4.116 prod() [3/3]
6.1.4.117 ptrace() [1/2]
6.1.4.118 ptrace() [2/2]
6.1.4.119 ptrace1() [1/2]
6.1.4.120 ptrace1() [2/2]
6.1.4.121 ptrace2() [1/2]
6.1.4.122 ptrace2() [2/2]
6.1.4.123 ptranspose() [1/2]
6.1.4.124 ptranspose() [2/2]
6.1.4.125 QFT()
6.1.4.126 qmutualinfo() [1/2] 9
6.1.4.127 qmutualinfo() [2/2] 9
6.1.4.128 rand() [1/5] 9
6.1.4.129 rand() [2/5] 9
6.1.4.130 rand() [3/5] 9
6.1.4.131 rand() [4/5] 9
6.1.4.132 rand() [5/5] 9
6.1.4.133 randH()
6.1.4.134 randidx()
6.1.4.135 randket()
6.1.4.136 randkraus()
6.1.4.137 randn() [1/4] 9
6.1.4.138 randn() [2/4]

6.1.4.139 randn() [3/4]
6.1.4.140 randn() [4/4]
6.1.4.141 randperm()
6.1.4.142 randprime()
6.1.4.143 randprob()
6.1.4.144 randrho()
6.1.4.145 randU()
6.1.4.146 randV()
6.1.4.147 renyi() [1/2]
6.1.4.148 renyi() [2/2]
6.1.4.149 reshape()
6.1.4.150 rho2bloch()
6.1.4.151 rho2pure()
6.1.4.152 save()
6.1.4.153 saveMATLAB() [1/2]
6.1.4.154 saveMATLAB() [2/2]
6.1.4.155 schatten()
6.1.4.156 schmidtA() [1/2]
6.1.4.157 schmidtA() [2/2]
6.1.4.158 schmidtB() [1/2]
6.1.4.159 schmidtB() [2/2]
6.1.4.160 schmidtcoeffs() [1/2]
6.1.4.161 schmidtcoeffs() [2/2]
6.1.4.162 schmidtprobs() [1/2]
6.1.4.163 schmidtprobs() [2/2]
6.1.4.164 sigma()
6.1.4.165 sinm()
6.1.4.166 spectralpowm()
6.1.4.167 sqrtm()
6.1.4.168 sum() [1/3]
6.1.4.169 sum() [2/3]
6.1.4.170 sum() [3/3]
6.1.4.171 super2choi()
6.1.4.172 svals()
6.1.4.173 svd()
6.1.4.174 svdU()
6.1.4.175 svdV()
6.1.4.176 syspermute() [1/2]
6.1.4.177 syspermute() [2/2]
6.1.4.178 TFQ()
6.1.4.179 trace()
6.1.4.180 transpose()

6.1.4.181 tsallis() [1/2]	115
6.1.4.182 tsallis() [2/2]	116
6.1.4.183 uniform()	116
6.1.4.184 var()	117
6.1.4.185 x2contfrac()	117
6.1.5 Variable Documentation	118
6.1.5.1 chop	118
6.1.5.2 ee	118
6.1.5.3 infty	118
6.1.5.4 maxn	118
6.1.5.5 pi	118
6.2 qpp::exception Namespace Reference	118
6.2.1 Detailed Description	120
6.3 qpp::experimental Namespace Reference	120
6.3.1 Detailed Description	120
6.4 qpp::internal Namespace Reference	120
6.4.1 Detailed Description	122
6.4.2 Function Documentation	122
6.4.2.1 abs_chop() [1/2]	122
6.4.2.2 abs_chop() [2/2]	122
6.4.2.3 check_cvector()	123
6.4.2.4 check_dims()	123
6.4.2.5 check_dims_match_cvect()	123
6.4.2.6 check_dims_match_mat()	123
6.4.2.7 check_dims_match_rvect()	123
6.4.2.8 check_eq_dims()	123
6.4.2.9 check_matching_sizes()	124
6.4.2.10 check_no_duplicates()	124
6.4.2.11 check_nonzero_size()	124
6.4.2.12 check_perm()	124
6.4.2.13 check_qubit_cvector()	124
6.4.2.14 check_qubit_matrix()	124
6.4.2.15 check_qubit_rvector()	125
6.4.2.16 check_qubit_vector()	125
6.4.2.17 check_rvector()	125
6.4.2.18 check_square_mat()	125
6.4.2.19 check_subsys_match_dims()	125
6.4.2.20 check_vector()	125
6.4.2.21 dirsum2()	126
6.4.2.22 get_dim_subsys()	126
6.4.2.23 get_num_subsys()	126
6.4.2.24 hash_combine()	126

6.4.2.25 kron2()	 126
6.4.2.26 multiidx2n()	 127
6.4.2.27 n2multiidx()	 127
6.4.2.28 variadic_vector_emplace() [1/2]	 127
6.4.2.29 variadic_vector_emplace() [2/2]	 127
6.5 qpp::literals Namespace Reference	 128
6.5.1 Function Documentation	 128
6.5.1.1 operator""""_bra()	 128
6.5.1.2 operator"""i() [1/2]	 129
6.5.1.3 operator"""i() [2/2]	 129
6.5.1.4 operator"""if() [1/2]	 129
6.5.1.5 operator"""if() [2/2]	 129
6.5.1.6 operator""""_ket()	 129
6.5.1.7 operator""""_prj()	 130
	404
7 Class Documentation	131
7.1 qpp::Bit_circuit Class Reference	
7.1.1 Detailed Description	
7.1.2 Constructor & Destructor Documentation	
7.1.2.1 Bit_circuit() [1/2]	
7.1.2.2 Bit_circuit() [2/2]	
7.1.2.3 ~Bit_circuit()	
7.1.3 Member Function Documentation	
7.1.3.1 CNOT()	
7.1.3.2 FRED()	
7.1.3.3 get_gate_count()	
7.1.3.4 get_gate_depth()	
7.1.3.5 NOT()	
7.1.3.6 reset()	
7.1.3.7 SWAP()	
7.1.3.8 TOF()	
7.1.3.9 X()	
7.1.4 Member Data Documentation	
7.1.4.1 bCNOT	
7.1.4.2 bFRED	 138
7.1.4.3 bNOT	 138
7.1.4.4 bSWAP	 138
7.1.4.5 bTOF	 138
7.1.4.6 btotal	 138
7.1.4.7 count	 139
7.1.4.8 depth	 139
7.2 app.:Codes Class Reference	130

7.2.1 Detailed Description	0
7.2.2 Member Enumeration Documentation	-0
7.2.2.1 Type	-C
7.2.3 Constructor & Destructor Documentation	-1
7.2.3.1 Codes()	-1
7.2.3.2 ~Codes()	-1
7.2.4 Member Function Documentation	-1
7.2.4.1 codeword()	-1
7.2.5 Friends And Related Function Documentation	-1
7.2.5.1 internal::Singleton < const Codes >	2
7.3 qpp::exception::CustomException Class Reference	2
7.3.1 Detailed Description	3
7.3.2 Constructor & Destructor Documentation	3
7.3.2.1 CustomException()	4
7.3.3 Member Function Documentation	4
7.3.3.1 description()	4
7.3.4 Member Data Documentation	4
7.3.4.1 what	4
7.4 qpp::exception::DimsInvalid Class Reference	5
7.4.1 Detailed Description	-6
7.4.2 Member Function Documentation	-6
7.4.2.1 description()	-6
7.4.2.2 Exception()	-6
7.5 qpp::exception::DimsMismatchCvector Class Reference	7
7.5.1 Detailed Description	8
7.5.2 Member Function Documentation	8
7.5.2.1 description()	8
7.5.2.2 Exception()	8
7.6 qpp::exception::DimsMismatchMatrix Class Reference	.9
7.6.1 Detailed Description	C
7.6.2 Member Function Documentation	Ю
7.6.2.1 description()	C
7.6.2.2 Exception()	C
7.7 qpp::exception::DimsMismatchRvector Class Reference	1
7.7.1 Detailed Description	2
7.7.2 Member Function Documentation	2
7.7.2.1 description()	2
7.7.2.2 Exception()	2
7.8 qpp::exception::DimsMismatchVector Class Reference	3
7.8.1 Detailed Description	i4
7.8.2 Member Function Documentation	14
7.8.2.1 description()	54

7.8.2.2 Exception()	54
7.9 qpp::exception::DimsNotEqual Class Reference	55
7.9.1 Detailed Description	56
7.9.2 Member Function Documentation	56
7.9.2.1 description()	56
7.9.2.2 Exception()	56
7.10 qpp::internal::Display_Impl_ Struct Reference	57
7.10.1 Member Function Documentation	57
7.10.1.1 display_impl_()	57
7.11 qpp::exception::Duplicates Class Reference	58
7.11.1 Detailed Description	59
7.11.2 Member Function Documentation	59
7.11.2.1 description()	59
7.11.2.2 Exception()	59
7.12 qpp::Dynamic_bitset Class Reference	59
7.12.1 Detailed Description	62
7.12.2 Member Typedef Documentation	62
7.12.2.1 storage_type	62
7.12.2.2 value_type	62
7.12.3 Constructor & Destructor Documentation	62
7.12.3.1 Dynamic_bitset()	62
7.12.3.2 ~Dynamic_bitset()	63
7.12.4 Member Function Documentation	63
7.12.4.1 all()	63
7.12.4.2 any()	63
7.12.4.3 count()	63
7.12.4.4 data()	64
7.12.4.5 display()	64
7.12.4.6 flip() [1/2]	64
7.12.4.7 flip() [2/2]	65
7.12.4.8 get()	65
7.12.4.9 index_()	65
7.12.4.10 none()	66
7.12.4.11 offset_()	66
7.12.4.12 operator"!=()	66
7.12.4.13 operator-()	67
7.12.4.14 operator==()	67
7.12.4.15 rand() [1/2]	67
7.12.4.16 rand() [2/2]	68
7.12.4.17 reset() [1/2]	68
7.12.4.18 reset() [2/2]	
7.12.4.19 set() [1/2]	69

7.12.4.20 set() [2/2]	39
7.12.4.21 size()	39
7.12.4.22 storage_size()	39
7.12.4.23 to_string()	70
7.12.5 Member Data Documentation	70
7.12.5.1 n	70
7.12.5.2 storage_size	70
7.12.5.3 v	71
7.13 qpp::internal::EqualEigen Class Reference	71
7.13.1 Detailed Description	71
7.13.2 Member Function Documentation	71
7.13.2.1 operator()()	71
7.14 qpp::internal::EqualSameSizeStringDits Class Reference	72
7.14.1 Detailed Description	72
7.14.2 Member Function Documentation	72
7.14.2.1 operator()()	72
7.15 qpp::exception::Exception Class Reference	73
7.15.1 Detailed Description	74
7.15.2 Constructor & Destructor Documentation	75
7.15.2.1 Exception()	75
7.15.3 Member Function Documentation	75
7.15.3.1 description()	75
7.15.3.2 what()	75
7.15.4 Member Data Documentation	⁷ 6
7.15.4.1 msg	76
7.15.4.2 where	76
7.16 qpp::Gates Class Reference	⁷ 6
7.16.1 Detailed Description	78
7.16.2 Constructor & Destructor Documentation	78
7.16.2.1 Gates()	78
7.16.2.2 ∼Gates()	79
7.16.3 Member Function Documentation	79
7.16.3.1 CTRL()	79
7.16.3.2 expandout() [1/3]	79
7.16.3.3 expandout() [2/3]	30
7.16.3.4 expandout() [3/3]	31
7.16.3.5 Fd()	31
7.16.3.6 get_name()	32
7.16.3.7 ld()	32
7.16.3.8 MODMUL()	33
7.16.3.9 Rn()	33
7.16.3.10 RX()	34

7.16.3.11 RY()		 	 	. 184
7.16.3.12 RZ()		 	 	. 184
7.16.3.13 SWAPd()		 	 	. 185
7.16.3.14 Xd()		 	 	. 185
7.16.3.15 Zd()		 	 	. 185
7.16.4 Friends And Related F	unction Documentation	 	 	. 186
7.16.4.1 internal::Sin	gleton< const Gates >	 	 	. 186
7.16.5 Member Data Docume	entation	 	 	. 186
7.16.5.1 CNOT		 	 	. 186
7.16.5.2 CNOTba .		 	 	. 186
7.16.5.3 CZ		 	 	. 186
7.16.5.4 FRED		 	 	. 187
7.16.5.5 H		 	 	. 187
7.16.5.6 ld2		 	 	. 187
7.16.5.7 S		 	 	. 187
7.16.5.8 SWAP		 	 	. 187
7.16.5.9 T		 	 	. 187
7.16.5.10 TOF		 	 	. 188
7.16.5.11 X		 	 	. 188
7.16.5.12 Y		 	 	. 188
7.16.5.13 Z		 	 	. 188
7.17 qpp::QCircuit::GateStep Struc	t Reference	 	 	. 189
7.17.1 Detailed Description		 	 	. 190
7.17.2 Constructor & Destruc	tor Documentation	 	 	. 190
7.17.2.1 GateStep()	[1/2]	 	 	. 190
7.17.2.2 GateStep()	[2/2]	 	 	. 190
7.17.3 Member Data Docume	entation	 	 	. 190
7.17.3.1 ctrl		 	 	. 190
7.17.3.2 gate_hash_		 	 	. 191
7.17.3.3 gate_type_		 	 	. 191
7.17.3.4 name		 	 	. 191
7.17.3.5 shift		 	 	. 191
7.17.3.6 target		 	 	. 191
7.18 qpp::internal::HashEigen Class	s Reference	 	 	. 191
7.18.1 Detailed Description		 	 	. 192
7.18.2 Member Function Doc	umentation	 	 	. 192
7.18.2.1 operator()()		 	 	. 192
7.19 qpp::IDisplay Class Reference		 	 	. 192
7.19.1 Detailed Description		 	 	. 193
7.19.2 Constructor & Destruc	tor Documentation	 	 	. 193
7.19.2.1 ∼IDisplay()		 	 	. 193
7.19.3 Member Function Doc	umentation	 	 	. 193

7.19.3.1 display()	193
7.19.4 Friends And Related Function Documentation	194
7.19.4.1 operator <<	194
7.20 qpp::IJSON Class Reference	194
7.20.1 Detailed Description	195
7.20.2 Constructor & Destructor Documentation	195
7.20.2.1 ∼IJSON()	195
7.20.3 Member Function Documentation	195
7.20.3.1 to_JSON()	195
7.21 qpp::ILayout Class Reference	195
7.21.1 Detailed Description	196
7.21.2 Constructor & Destructor Documentation	196
7.21.2.1 ∼ILayout()	196
7.21.3 Member Function Documentation	196
7.21.3.1 get_dims()	197
7.21.3.2 operator()()	197
7.21.3.3 to_coordinates()	197
7.22 qpp::Init Class Reference	198
7.22.1 Detailed Description	199
7.22.2 Constructor & Destructor Documentation	199
7.22.2.1 Init()	199
7.22.2.2 ~Init()	199
7.22.3 Friends And Related Function Documentation	199
7.22.3.1 internal::Singleton< const Init >	199
7.23 qpp::exception::InvalidIterator Class Reference	200
7.23.1 Detailed Description	201
7.23.2 Member Function Documentation	201
7.23.2.1 description()	201
7.23.2.2 Exception()	201
7.24 qpp::internal::IOManipEigen Class Reference	202
7.24.1 Constructor & Destructor Documentation	203
7.24.1.1 IOManipEigen() [1/2]	203
7.24.1.2 IOManipEigen() [2/2]	203
7.24.2 Member Function Documentation	203
7.24.2.1 display()	203
7.24.3 Member Data Documentation	203
7.24.3.1 A	204
7.24.3.2 chop	204
7.25 qpp::internal::IOManipPointer < PointerType > Class Template Reference	204
7.25.1 Constructor & Destructor Documentation	205
7.25.1.1 IOManipPointer() [1/2]	206
7.25.1.2 IOManipPointer() [2/2]	206

7.25.2 Member Function Documentation
7.25.2.1 display()
7.25.2.2 operator=()
7.25.3 Member Data Documentation
7.25.3.1 chop
7.25.3.2 end
7.25.3.3 N __
7.25.3.4 p
7.25.3.5 separator
7.25.3.6 start
7.26 qpp::internal::IOManipRange< InputIterator > Class Template Reference
7.26.1 Constructor & Destructor Documentation
7.26.1.1 IOManipRange() [1/2]
7.26.1.2 IOManipRange() [2/2]
7.26.2 Member Function Documentation
7.26.2.1 display()
7.26.2.2 operator=()
7.26.3 Member Data Documentation
7.26.3.1 chop
7.26.3.2 end
7.26.3.3 first
7.26.3.4 last
7.26.3.5 separator
7.26.3.6 start
$7.27 \; qpp::is_complex < T > Struct \; Template \; Reference \; \ldots \qquad \qquad$
7.27.1 Detailed Description
7.28 qpp::is_complex $<$ std::complex $<$ T $>$ $>$ Struct Template Reference
7.28.1 Detailed Description
7.29 qpp::is_iterable < T, typename > Struct Template Reference
7.29.1 Detailed Description
7.30 qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval< T >().end()), decltype(*(std::declval< T >().begin()))> > Struct Template Reference
7.30.1 Detailed Description
7.31 qpp::is_matrix_expression< Derived > Struct Template Reference
7.31.1 Detailed Description
7.32 qpp::QCircuit::iterator Class Reference
7.32.1 Detailed Description
7.32.2 Member Typedef Documentation
7.32.2.1 difference_type
7.32.2.2 iterator_category
7.32.2.3 pointer
7.32.2.4 reference

7.32.2.5 value_type
7.32.3 Constructor & Destructor Documentation
7.32.3.1 iterator() [1/2]
7.32.3.2 iterator() [2/2]
7.32.4 Member Function Documentation
7.32.4.1 operator *()
7.32.4.2 operator"!=()
7.32.4.3 operator++() [1/2]
7.32.4.4 operator++() [2/2]
7.32.4.5 operator=()
7.32.4.6 operator==()
7.32.4.7 set_begin_()
7.32.4.8 set_end_()
7.32.5 Member Data Documentation
7.32.5.1 elem
7.32.5.2 qc
7.33 qpp::Lattice Class Reference
7.33.1 Detailed Description
7.33.2 Constructor & Destructor Documentation
7.33.2.1 Lattice() [1/2]
7.33.2.2 Lattice() [2/2]
7.33.3 Member Function Documentation
7.33.3.1 compute_()
7.33.3.2 get_dims()
7.33.3.3 operator()() [1/2]
7.33.3.4 operator()() [2/2]
7.33.3.5 prod_dims()
7.33.3.6 to_coordinates()
7.33.4 Member Data Documentation
7.33.4.1 dims
7.34 qpp::make_void < Ts > Struct Template Reference
7.34.1 Detailed Description
7.34.2 Member Typedef Documentation
7.34.2.1 type
7.35 qpp::exception::MatrixMismatchSubsys Class Reference
7.35.1 Detailed Description
7.35.2 Member Function Documentation
7.35.2.1 description()
7.35.2.2 Exception()
7.36 qpp::exception::MatrixNotCvector Class Reference
7.36.1 Detailed Description
7.36.2 Member Function Documentation

7.36.2.1 description()	231
7.36.2.2 Exception()	231
7.37 qpp::exception::MatrixNotRvector Class Reference	232
7.37.1 Detailed Description	233
7.37.2 Member Function Documentation	233
7.37.2.1 description()	233
7.37.2.2 Exception()	233
7.38 qpp::exception::MatrixNotSquare Class Reference	234
7.38.1 Detailed Description	235
7.38.2 Member Function Documentation	235
7.38.2.1 description()	235
7.38.2.2 Exception()	235
7.39 qpp::exception::MatrixNotSquareNorCvector Class Reference	236
7.39.1 Detailed Description	237
7.39.2 Member Function Documentation	237
7.39.2.1 description()	237
7.39.2.2 Exception()	237
7.40 qpp::exception::MatrixNotSquareNorRvector Class Reference	238
7.40.1 Detailed Description	239
7.40.2 Member Function Documentation	239
7.40.2.1 description()	239
7.40.2.2 Exception()	239
7.41 qpp::exception::MatrixNotSquareNorVector Class Reference	240
7.41.1 Detailed Description	241
7.41.2 Member Function Documentation	241
7.41.2.1 description()	241
7.41.2.2 Exception()	241
7.42 qpp::exception::MatrixNotVector Class Reference	242
7.42.1 Detailed Description	243
7.42.2 Member Function Documentation	243
7.42.2.1 description()	243
7.42.2.2 Exception()	243
7.43 qpp::QCircuit::MeasureStep Struct Reference	244
7.43.1 Detailed Description	244
7.43.2 Constructor & Destructor Documentation	245
7.43.2.1 MeasureStep() [1/2]	245
7.43.2.2 MeasureStep() [2/2]	245
7.43.3 Member Data Documentation	245
7.43.3.1 c_reg	245
7.43.3.2 mats_hash	245
7.43.3.3 measurement_type	246
7.43.3.4 name	246

7.43.3.5 target
7.44 qpp::exception::NoCodeword Class Reference
7.44.1 Detailed Description
7.44.2 Member Function Documentation
7.44.2.1 description()
7.44.2.2 Exception()
7.45 qpp::NoiseBase $<$ T $>$ Class Template Reference
7.45.1 Detailed Description
7.45.2 Member Typedef Documentation
7.45.2.1 noise_type
7.45.3 Constructor & Destructor Documentation
7.45.3.1 NoiseBase() [1/2]
7.45.3.2 NoiseBase() [2/2]
7.45.3.3 ~NoiseBase()
7.45.4 Member Function Documentation
7.45.4.1 compute_probs_()
7.45.4.2 compute_state_()
7.45.4.3 get_d()
7.45.4.4 get_Ks()
7.45.4.5 get_last_idx()
7.45.4.6 get_last_K()
7.45.4.7 get_last_p()
7.45.4.8 get_probs()
7.45.4.9 operator()() [1/3]
7.45.4.10 operator()() [2/3]
7.45.4.11 operator()() [3/3]
7.45.5 Member Data Documentation
7.45.5.1 d
7.45.5.2 generated
7.45.5.3 i
7.45.5.4 Ks
7.45.5.5 probs
7.46 qpp::NoiseType Class Reference
7.46.1 Detailed Description
7.47 qpp::exception::NotBipartite Class Reference
7.47.1 Detailed Description
7.47.2 Member Function Documentation
7.47.2.1 description()
7.47.2.2 Exception()
7.48 qpp::exception::NotImplemented Class Reference
7.48.1 Detailed Description
7.48.2 Member Function Documentation

7.48.2.1 description()
7.48.2.2 Exception()
7.49 qpp::exception::NotQubitCvector Class Reference
7.49.1 Detailed Description
7.49.2 Member Function Documentation
7.49.2.1 description()
7.49.2.2 Exception()
7.50 qpp::exception::NotQubitMatrix Class Reference
7.50.1 Detailed Description
7.50.2 Member Function Documentation
7.50.2.1 description()
7.50.2.2 Exception()
7.51 qpp::exception::NotQubitRvector Class Reference
7.51.1 Detailed Description
7.51.2 Member Function Documentation
7.51.2.1 description()
7.51.2.2 Exception()
7.52 qpp::exception::NotQubitSubsys Class Reference
7.52.1 Detailed Description
7.52.2 Member Function Documentation
7.52.2.1 description()
7.52.2.2 Exception()
7.53 qpp::exception::NotQubitVector Class Reference
7.53.1 Detailed Description
7.53.2 Member Function Documentation
7.53.2.1 description()
7.53.2.2 Exception()
7.54 qpp::exception::OutOfRange Class Reference
7.54.1 Detailed Description
7.54.2 Member Function Documentation
7.54.2.1 description()
7.54.2.2 Exception()
7.55 qpp::exception::PermInvalid Class Reference
7.55.1 Detailed Description
7.55.2 Member Function Documentation
7.55.2.1 description()
7.55.2.2 Exception()
7.56 qpp::exception::PermMismatchDims Class Reference
7.56.1 Detailed Description
7.56.2 Member Function Documentation
7.56.2.1 description()
7.56.2.2 Exception()

7.57 qpp::QCircuit Class Reference	77
7.57.1 Detailed Description	81
7.57.2 Member Typedef Documentation	82
7.57.2.1 const_iterator	82
7.57.3 Member Enumeration Documentation	82
7.57.3.1 GateType	82
7.57.3.2 MeasureType	83
7.57.3.3 StepType	83
7.57.4 Constructor & Destructor Documentation	83
7.57.4.1 QCircuit()	83
7.57.4.2 ~QCircuit()	84
7.57.5 Member Function Documentation	84
7.57.5.1 add_circuit()	84
7.57.5.2 add_dit()	85
7.57.5.3 add_hash_()	85
7.57.5.4 add_qudit()	86
7.57.5.5 adjoint()	86
7.57.5.6 begin() [1/2]	86
7.57.5.7 begin() [2/2]	87
7.57.5.8 cbegin()	87
7.57.5.9 cCTRL() [1/4]	87
7.57.5.10 cCTRL() [2/4]	88
7.57.5.11 cCTRL() [3/4]	88
7.57.5.12 cCTRL() [4/4]	89
7.57.5.13 cCTRL_custom()	89
7.57.5.14 cend()	90
7.57.5.15 CTRL() [1/4]	90
7.57.5.16 CTRL() [2/4]	90
7.57.5.17 CTRL() [3/4]	91
7.57.5.18 CTRL() [4/4]	91
7.57.5.19 CTRL_custom()	92
7.57.5.20 display()	92
7.57.5.21 end() [1/2]	93
7.57.5.22 end() [2/2]	93
7.57.5.23 gate() [1/3] 2	93
7.57.5.24 gate() [2/3] 2	94
7.57.5.25 gate() [3/3] 2	94
7.57.5.26 gate_custom()	95
7.57.5.27 gate_fan() [1/3]	95
7.57.5.28 gate_fan() [2/3]	96
7.57.5.29 gate_fan() [3/3]	96
7.57.5.30 get cmat hash tbl ()	96

7.57.5.31 get_d())7
7.57.5.32 get_depth())7
7.57.5.33 get_gate_count())7
7.57.5.34 get_gates_()	8(
7.57.5.35 get_measured() [1/2]	98
7.57.5.36 get_measured() [2/2]	98
7.57.5.37 get_measurement_count() [1/2]	9
7.57.5.38 get_measurement_count() [2/2]	9
7.57.5.39 get_measurements_()) 9
7.57.5.40 get_name()	9
7.57.5.41 get_nc())0
7.57.5.42 get_non_measured())0
7.57.5.43 get_nop_count())0
7.57.5.44 get_nq())0
7.57.5.45 get_step_count())1
7.57.5.46 kron())1
7.57.5.47 measureV() [1/2])2
7.57.5.48 measureV() [2/2])2
7.57.5.49 measureZ() [1/2])3
7.57.5.50 measureZ() [2/2])3
7.57.5.51 nop())4
7.57.5.52 QFT() [1/3])4
7.57.5.53 QFT() [2/3])4
7.57.5.54 QFT() [3/3])5
7.57.5.55 replicate())5
7.57.5.56 TFQ() [1/3])5
7.57.5.57 TFQ() [2/3])7
7.57.5.58 TFQ() [3/3])7
7.57.5.59 to_JSON()	8(
7.57.6 Friends And Related Function Documentation)8
7.57.6.1 add_circuit)8
7.57.6.2 adjoint)9
7.57.6.3 kron)9
7.57.6.4 operator<< [1/4])9
7.57.6.5 operator<< [2/4]	0
7.57.6.6 operator << [3/4]	0
7.57.6.7 operator<< [4/4]	1
7.57.6.8 QEngine	1
7.57.6.9 replicate	1
7.57.7 Member Data Documentation	1
7.57.7.1 cmat_hash_tbl	2
7.57.7.2 count	2

7.57.7.3 d	312
7.57.7.4 gates	312
7.57.7.5 measured	312
7.57.7.6 measurement_count	312
7.57.7.7 measurements	313
7.57.7.8 name	313
7.57.7.9 nc	313
7.57.7.10 nq	313
7.57.7.11 step_types	313
7.58 qpp::QEngine Class Reference	314
7.58.1 Detailed Description	316
7.58.2 Constructor & Destructor Documentation	316
7.58.2.1 QEngine() [1/3]	316
7.58.2.2 QEngine() [2/3]	317
7.58.2.3 QEngine() [3/3]	317
7.58.2.4 ~QEngine()	317
7.58.3 Member Function Documentation	317
7.58.3.1 display()	317
7.58.3.2 execute() [1/3]	318
7.58.3.3 execute() [2/3]	318
7.58.3.4 execute() [3/3]	318
7.58.3.5 get_circuit()	319
7.58.3.6 get_dit()	319
7.58.3.7 get_dits()	319
7.58.3.8 get_measured() [1/2]	319
7.58.3.9 get_measured() [2/2]	320
7.58.3.10 get_non_measured()	320
7.58.3.11 get_probs()	320
7.58.3.12 get_psi()	321
7.58.3.13 get_relative_pos_()	321
7.58.3.14 get_stats()	321
7.58.3.15 operator=()	321
7.58.3.16 reset()	322
7.58.3.17 reset_stats()	322
7.58.3.18 set_dit()	322
7.58.3.19 set_measured_()	322
7.58.3.20 set_psi()	323
7.58.3.21 to_JSON()	323
7.58.4 Member Data Documentation	323
7.58.4.1 qc	324
7.58.4.2 st	324
7.58.4.3 stats	324

7.59 qpp::QNoisyEngine < NoiseModel > Class Template Reference
7.59.1 Detailed Description
7.59.2 Constructor & Destructor Documentation
7.59.2.1 QNoisyEngine()
7.59.3 Member Function Documentation
7.59.3.1 execute() [1/4]
7.59.3.2 execute() [2/4]
7.59.3.3 execute() [3/4]
7.59.3.4 execute() [4/4]
7.59.3.5 get_noise_results()
7.59.4 Member Data Documentation
7.59.4.1 noise
7.59.4.2 noise_results
7.60 qpp::QubitAmplitudeDampingNoise Class Reference
7.60.1 Detailed Description
7.60.2 Constructor & Destructor Documentation
7.60.2.1 QubitAmplitudeDampingNoise()
7.61 qpp::QubitBitFlipNoise Class Reference
7.61.1 Detailed Description
7.61.2 Constructor & Destructor Documentation
7.61.2.1 QubitBitFlipNoise()
7.62 qpp::QubitBitPhaseFlipNoise Class Reference
7.62.1 Detailed Description
7.62.2 Constructor & Destructor Documentation
7.62.2.1 QubitBitPhaseFlipNoise()
7.63 qpp::QubitDepolarizingNoise Class Reference
7.63.1 Detailed Description
7.63.2 Constructor & Destructor Documentation
7.63.2.1 QubitDepolarizingNoise()
7.64 qpp::QubitPhaseDampingNoise Class Reference
7.64.1 Detailed Description
7.64.2 Constructor & Destructor Documentation
7.64.2.1 QubitPhaseDampingNoise()
7.65 qpp::QubitPhaseFlipNoise Class Reference
7.65.1 Detailed Description
7.65.2 Constructor & Destructor Documentation
7.65.2.1 QubitPhaseFlipNoise()
7.66 qpp::exception::QuditAlreadyMeasured Class Reference
7.66.1 Detailed Description
7.66.2 Member Function Documentation
7.66.2.1 description()
7.66.2.2 Exception()

7.67 qpp::QuditDepolarizingNoise Class Reference
7.67.1 Detailed Description
7.67.2 Constructor & Destructor Documentation
7.67.2.1 QuditDepolarizingNoise()
7.67.3 Member Function Documentation
7.67.3.1 fill_Ks_()
7.67.3.2 fill_probs_()
7.68 qpp::RandomDevices Class Reference
7.68.1 Detailed Description
7.68.2 Constructor & Destructor Documentation
7.68.2.1 RandomDevices()
7.68.2.2 ~RandomDevices()
7.68.3 Member Function Documentation
7.68.3.1 get_prng()
7.68.3.2 load()
7.68.3.3 save()
7.68.4 Friends And Related Function Documentation
7.68.4.1 internal::Singleton < RandomDevices >
7.68.5 Member Data Documentation
7.68.5.1 prng
7.68.5.2 rd
7.69 qpp::internal::Singleton< T > Class Template Reference
7.69.1 Detailed Description
7.69.2 Constructor & Destructor Documentation
7.69.2.1 Singleton() [1/2]
7.69.2.2 Singleton() [2/2]
7.69.2.3 ~Singleton()
7.69.3 Member Function Documentation
7.69.3.1 get_instance()
7.69.3.2 get_thread_local_instance()
7.69.3.3 operator=()
7.70 qpp::exception::SizeMismatch Class Reference
7.70.1 Detailed Description
7.70.2 Member Function Documentation
7.70.2.1 description()
7.70.2.2 Exception()
7.71 qpp::QEngine::state_ Class Reference
7.71.1 Detailed Description
7.71.2 Constructor & Destructor Documentation
7.71.2.1 state_() [1/2]
7.71.2.2 state_() [2/2]
7.71.3 Member Function Documentation

7.71.3.1 operator=()	51
7.71.3.2 reset()	51
7.71.4 Member Data Documentation	52
7.71.4.1 dits	52
7.71.4.2 probs	52
7.71.4.3 psi	52
7.71.4.4 qc	52
7.71.4.5 subsys	52
7.72 qpp::NoiseType::StateDependent Class Reference	53
7.72.1 Detailed Description	53
7.73 qpp::NoiseType::StateIndependent Class Reference	53
7.73.1 Detailed Description	53
7.74 qpp::States Class Reference	53
7.74.1 Detailed Description	55
7.74.2 Constructor & Destructor Documentation	56
7.74.2.1 States()	56
7.74.2.2 ~States()	56
7.74.3 Member Function Documentation	56
7.74.3.1 jn()	56
7.74.3.2 mes()	56
7.74.3.3 minus()	57
7.74.3.4 one()	57
7.74.3.5 plus()	58
7.74.3.6 zero()	58
7.74.4 Friends And Related Function Documentation	58
7.74.4.1 internal::Singleton < const States >	58
7.74.5 Member Data Documentation	58
7.74.5.1 b00	59
7.74.5.2 b01	59
7.74.5.3 b10	59
7.74.5.4 b11	59
7.74.5.5 GHZ	59
7.74.5.6 pb00	59
7.74.5.7 pb01	60
7.74.5.8 pb10	60
7.74.5.9 pb11	60
7.74.5.10 pGHZ	60
7.74.5.11 pW	60
7.74.5.12 px0	60
7.74.5.13 px1	61
7.74.5.14 py0	61
7.74.5.15 py1	61

7.74.5.16 pz0	61
7.74.5.17 pz1	61
7.74.5.18 W	61
7.74.5.19 x0	62
7.74.5.20 x1	62
7.74.5.21 y0	62
7.74.5.22 y1	62
7.74.5.23 z0	62
7.74.5.24 z1	62
7.75 qpp::exception::SubsysMismatchDims Class Reference	63
7.75.1 Detailed Description	64
7.75.2 Member Function Documentation	64
7.75.2.1 description()	64
7.75.2.2 Exception()	64
7.76 qpp::Timer< T, CLOCK_T > Class Template Reference	65
7.76.1 Detailed Description	66
7.76.2 Constructor & Destructor Documentation	66
7.76.2.1 Timer()	66
7.76.2.2 ~Timer()	66
7.76.3 Member Function Documentation	67
7.76.3.1 display()	67
7.76.3.2 get_duration()	67
7.76.3.3 tic()	68
7.76.3.4 tics()	68
7.76.3.5 toc()	68
7.76.4 Member Data Documentation	68
7.76.4.1 end	68
7.76.4.2 start	69
7.77 qpp::exception::TypeMismatch Class Reference	69
7.77.1 Detailed Description	70
7.77.2 Member Function Documentation	70
7.77.2.1 description()	70
7.77.2.2 Exception()	71
7.78 qpp::exception::UndefinedType Class Reference	71
7.78.1 Detailed Description	72
7.78.2 Member Function Documentation	72
7.78.2.1 description()	72
7.78.2.2 Exception()	73
7.79 qpp::exception::Unknown Class Reference	73
7.79.1 Detailed Description	74
7.79.2 Member Function Documentation	74
7.79.2.1 description()	74

	7.79.2.2 Exception()	375
	7.80 qpp::QCircuit::iterator::value_type_ Class Reference	375
	7.80.1 Detailed Description	376
	7.80.2 Constructor & Destructor Documentation	376
	7.80.2.1 value_type_() [1/2]	376
	7.80.2.2 value_type_() [2/2]	377
	7.80.3 Member Function Documentation	377
	7.80.3.1 display()	377
	7.80.3.2 operator=()	377
	7.80.4 Member Data Documentation	377
	7.80.4.1 gates_ip	378
	7.80.4.2 ip	378
	7.80.4.3 measurements_ip	378
	7.80.4.4 type	378
	7.80.4.5 value_type_qc	378
	7.81 qpp::exception::ZeroSize Class Reference	379
	7.81.1 Detailed Description	380
	7.81.2 Member Function Documentation	380
	7.81.2.1 description()	380
	7.81.2.2 Exception()	380
Ω	File Documentation	381
Ü	8.1 classes/circuits/circuits.h File Reference	301
		321
	8.1.1 Detailed Description	382
	8.1.1 Detailed Description	382 382
	8.1.1 Detailed Description	382 382 382
	8.1.1 Detailed Description	382 382 382 383
	8.1.1 Detailed Description	382 382 382 383 383
	8.1.1 Detailed Description	382 382 383 383 383
	8.1.1 Detailed Description 8.2 classes/circuits/engines.h File Reference 8.2.1 Detailed Description 8.3 classes/codes.h File Reference 8.3.1 Detailed Description 8.4 classes/exception.h File Reference 8.4.1 Detailed Description	382 382 383 383 383 385
	8.1.1 Detailed Description 8.2 classes/circuits/engines.h File Reference 8.2.1 Detailed Description 8.3 classes/codes.h File Reference 8.3.1 Detailed Description 8.4 classes/exception.h File Reference 8.4.1 Detailed Description 8.5 classes/gates.h File Reference	382 382 383 383 383 385 385
	8.1.1 Detailed Description 8.2 classes/circuits/engines.h File Reference 8.2.1 Detailed Description 8.3 classes/codes.h File Reference 8.3.1 Detailed Description 8.4 classes/exception.h File Reference 8.4.1 Detailed Description 8.5 classes/gates.h File Reference 8.5.1 Detailed Description	382 382 383 383 383 385 385 386
	8.1.1 Detailed Description 8.2 classes/circuits/engines.h File Reference 8.2.1 Detailed Description 8.3 classes/codes.h File Reference 8.3.1 Detailed Description 8.4 classes/exception.h File Reference 8.4.1 Detailed Description 8.5 classes/gates.h File Reference 8.5.1 Detailed Description 8.6 classes/idisplay.h File Reference	382 382 383 383 383 385 386 386
	8.1.1 Detailed Description 8.2 classes/circuits/engines.h File Reference 8.2.1 Detailed Description 8.3 classes/codes.h File Reference 8.3.1 Detailed Description 8.4 classes/exception.h File Reference 8.4.1 Detailed Description 8.5 classes/gates.h File Reference 8.5.1 Detailed Description 8.6 classes/idisplay.h File Reference 8.6.1 Detailed Description	382 382 383 383 383 385 385 386 386 387
	8.1.1 Detailed Description 8.2 classes/circuits/engines.h File Reference 8.2.1 Detailed Description 8.3 classes/codes.h File Reference 8.3.1 Detailed Description 8.4 classes/exception.h File Reference 8.4.1 Detailed Description 8.5 classes/gates.h File Reference 8.5.1 Detailed Description 8.6 classes/idisplay.h File Reference 8.6.1 Detailed Description 8.7 classes/init.h File Reference	382 382 383 383 383 385 386 386
	8.1.1 Detailed Description 8.2 classes/circuits/engines.h File Reference 8.2.1 Detailed Description 8.3 classes/codes.h File Reference 8.3.1 Detailed Description 8.4 classes/exception.h File Reference 8.4.1 Detailed Description 8.5 classes/gates.h File Reference 8.5.1 Detailed Description 8.6 classes/idisplay.h File Reference 8.6.1 Detailed Description 8.7 classes/init.h File Reference 8.7.1 Detailed Description	382 382 383 383 385 385 386 386 387
	8.1.1 Detailed Description 8.2 classes/circuits/engines.h File Reference 8.2.1 Detailed Description 8.3 classes/codes.h File Reference 8.3.1 Detailed Description 8.4 classes/exception.h File Reference 8.4.1 Detailed Description 8.5 classes/gates.h File Reference 8.5.1 Detailed Description 8.6 classes/idisplay.h File Reference 8.6.1 Detailed Description 8.7 classes/init.h File Reference 8.7.1 Detailed Description 8.8 classes/layouts.h File Reference	382 382 383 383 383 385 386 386 387 387 387
	8.1.1 Detailed Description 8.2 classes/circuits/engines.h File Reference 8.2.1 Detailed Description 8.3 classes/codes.h File Reference 8.3.1 Detailed Description 8.4 classes/exception.h File Reference 8.4.1 Detailed Description 8.5 classes/gates.h File Reference 8.5.1 Detailed Description 8.6 classes/idisplay.h File Reference 8.6.1 Detailed Description 8.7 classes/init.h File Reference 8.7.1 Detailed Description 8.8 classes/layouts.h File Reference 8.8.1 Detailed Description	382 382 383 383 383 385 385 386 387 387 387 388 388
	8.1.1 Detailed Description 8.2 classes/circuits/engines.h File Reference 8.2.1 Detailed Description 8.3 classes/codes.h File Reference 8.3.1 Detailed Description 8.4 classes/exception.h File Reference 8.4.1 Detailed Description 8.5 classes/gates.h File Reference 8.5.1 Detailed Description 8.6 classes/idisplay.h File Reference 8.6.1 Detailed Description 8.7 classes/init.h File Reference 8.7.1 Detailed Description 8.8 classes/layouts.h File Reference 8.8.1 Detailed Description 8.9 classes/noise.h File Reference	382 382 383 383 383 385 385 386 387 387 387 388 388
	8.1.1 Detailed Description 8.2 classes/circuits/engines.h File Reference 8.2.1 Detailed Description 8.3 classes/codes.h File Reference 8.3.1 Detailed Description 8.4 classes/exception.h File Reference 8.4.1 Detailed Description 8.5 classes/gates.h File Reference 8.5.1 Detailed Description 8.6 classes/idisplay.h File Reference 8.6.1 Detailed Description 8.7 classes/init.h File Reference 8.7.1 Detailed Description 8.8 classes/layouts.h File Reference 8.8.1 Detailed Description	382 382 383 383 383 385 385 386 387 387 387 388 388
	8.1.1 Detailed Description 8.2 classes/circuits/engines.h File Reference 8.2.1 Detailed Description 8.3 classes/codes.h File Reference 8.3.1 Detailed Description 8.4 classes/exception.h File Reference 8.4.1 Detailed Description 8.5 classes/gates.h File Reference 8.5.1 Detailed Description 8.6 classes/idisplay.h File Reference 8.6.1 Detailed Description 8.7 classes/init.h File Reference 8.7.1 Detailed Description 8.8 classes/layouts.h File Reference 8.8.1 Detailed Description 8.8 classes/layouts.h File Reference 8.9.1 Detailed Description	382 382 383 383 383 385 385 386 387 387 387 388 388 389 390

8.11 classes/reversible.h File Reference	0
8.11.1 Detailed Description	11
8.12 classes/states.h File Reference	1
8.12.1 Detailed Description	2
8.13 classes/timer.h File Reference	12
8.13.1 Detailed Description	12
8.14 constants.h File Reference	3
8.14.1 Detailed Description	14
8.15 entanglement.h File Reference	14
8.15.1 Detailed Description	6
8.16 entropies.h File Reference	6
8.16.1 Detailed Description	17
8.17 experimental/experimental.h File Reference	17
8.17.1 Detailed Description	17
8.18 functions.h File Reference	17
8.18.1 Detailed Description	12
8.19 input_output.h File Reference	12
8.19.1 Detailed Description	13
8.20 instruments.h File Reference	13
8.20.1 Detailed Description	15
8.21 internal/classes/iomanip.h File Reference	15
8.21.1 Detailed Description	15
8.22 internal/classes/singleton.h File Reference	16
8.22.1 Detailed Description	16
8.23 internal/util.h File Reference	16
8.23.1 Detailed Description	18
8.24 MATLAB/matlab.h File Reference	18
8.24.1 Detailed Description	19
8.25 number_theory.h File Reference	19
8.25.1 Detailed Description	0
8.26 operations.h File Reference	1
8.26.1 Detailed Description	3
8.27 qpp.h File Reference	3
8.27.1 Detailed Description	4
8.27.2 Macro Definition Documentation	4
8.27.2.1 QPP_UNUSED	4
8.28 random.h File Reference	5
8.28.1 Detailed Description	6
8.29 statistics.h File Reference	6
8.29.1 Detailed Description	7
8.30 traits.h File Reference	7
8.30.1 Detailed Description	8

	XXVI
8.31 types.h File Reference	 . 419
8.31.1 Detailed Description	 . 420
8.32 /Users/vlad/qpp/README.md File Reference	 . 420
Index	421

Chapter 1

Quantum++

Version 1.3 - 25 July 2019

Build status:

Chat (questions/issues)

About

Quantum++ is a modern C++11 general purpose quantum computing library, composed solely of template header files. Quantum++ is written in standard C++11 and has very low external dependencies, using only the Eigen 3 linear algebra header-only template library and, if available, the OpenMP multi-processing library.

Quantum++ is not restricted to qubit systems or specific quantum information processing tasks, being capable of simulating arbitrary quantum processes. The main design factors taken in consideration were the ease of use, high portability, and high performance. The library's simulation capabilities are only restricted by the amount of available physical memory. On a typical machine (Intel i5 8Gb RAM) Quantum++ can successfully simulate the evolution of 25 qubits in a pure state or of 12 qubits in a mixed state reasonably fast.

To report any bugs or ask for additional features/enhancements, please submit an issue with an appropriate label.

If you are interesting in contributing to this project, feel free to contact me. Alternatively, create a custom branch, add your contribution, then finally create a pull request. If I accept the pull request, I will merge your custom branch with the latest development branch. The latter will eventually be merged into a future release version. To contribute, you need to have a solid knowledge of C++ (preferably C++11), including templates and the standard library, a basic knowledge of quantum computing and linear algebra, and working experience with Eigen 3.

For additional Eigen 3 documentation see http://eigen.tuxfamily.org/dox/. For a simple Eigen 3 quick ASCII reference see http://eigen.tuxfamily.org/dox/AsciiQuick← Reference.txt.

Copyright (c) 2013 - 2019 Vlad Gheorghiu, vgheorgh AT gmail DOT com.

2 Quantum++

License

Quantum++ is distributed under the MIT license. Please see the LICENSE file for more details.

Installation instructions and further documentation

Please see the installation guide `INSTALL.md` and the comprehensive Wiki for further documentation and detailed examples.

The official API documentation is available in PDF and HTML formats in the doc folder.

Chapter 2

Namespace Index

2.1 Namespace List

Here is a list of all namespaces with brief descriptions:

qpp	
Quantum++ main namespace	Ę
qpp::exception	
Quantum++ exception hierarchy namespace	8
qpp::experimental	
Experimental/test functions/classes, do not use or modify	2(
qpp::internal	
Internal utility functions, do not use them directly or modify them	20
qpp::literals	35

4 Namespace Index

Chapter 3

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

qpp::internal::Display_Impl
qpp::internal::IOManipEigen
qpp::internal::EqualEigen
qpp::internal::EqualSameSizeStringDits
std::exception
qpp::exception::Exception
qpp::exception::CustomException
gpp::exception::DimsInvalid
qpp::exception::DimsMismatchCvector
qpp::exception::DimsMismatchMatrix
qpp::exception::DimsMismatchRvector
qpp::exception::DimsMismatchVector
gpp::exception::DimsNotEqual
qpp::exception::Duplicates
qpp::exception::InvalidIterator
qpp::exception::MatrixMismatchSubsys
qpp::exception::MatrixNotCvector
qpp::exception::MatrixNotRvector
qpp::exception::MatrixNotSquare
qpp::exception::MatrixNotSquareNorCvector
qpp::exception::MatrixNotSquareNorRvector
qpp::exception::MatrixNotSquareNorVector
qpp::exception::MatrixNotVector
qpp::exception::NoCodeword
qpp::exception::NotBipartite
qpp::exception::NotImplemented
qpp::exception::NotQubitCvector
qpp::exception::NotQubitMatrix
qpp::exception::NotQubitRvector
qpp::exception::NotQubitSubsys
qpp::exception::NotQubitVector
qpp::exception::OutOfRange
qpp::exception::PermInvalid
qpp::exception::PermMismatchDims
qpp::exception::QuditAlreadyMeasured

6 Hierarchical Index

qpp::exception::SizeMismatch	18
qpp::exception::SubsysMismatchDims	
qpp::exception::TypeMismatch	
qpp::exception::UndefinedType	
qpp::exception::Unknown	
qpp::exception::ZeroSize	79
false_type	
qpp::is_complex< T >	
qpp::is_iterable < T, typename >	
qpp::QCircuit::GateStep	
qpp::internal::HashEigen	
qpp::IDisplay	
qpp::Dynamic_bitset	
qpp::Bit_circuit	
qpp::internal::IOManipEigen	
qpp::internal::IOManipPointer< PointerType >	
qpp::internal::IOManipRange< InputIterator >	
qpp::QCircuit	
qpp::QCircuit::iterator::value_type	
qpp::QEngine	
qpp::QNoisyEngine < NoiseModel >	
qpp::Timer< T, CLOCK_T >	
qpp::IJSON	}4
qpp::QCircuit	77
qpp::QEngine	14
qpp::ILayout	3 5
qpp::Lattice	22
is base of	
qpp::is matrix expression< Derived >	16
qpp::QCircuit::iterator	
qpp::make_void < Ts >	27
qpp::QCircuit::MeasureStep	14
$qpp::NoiseBase < T > \dots \dots$	1 8
$qpp:: Noise Base < Noise Type:: State Dependent > \dots $	18
qpp::QubitAmplitudeDampingNoise	28
qpp::QubitPhaseDampingNoise	34
qpp::NoiseBase < NoiseType::StateIndependent >	18
qpp::QubitBitFlipNoise	30
qpp::QubitBitPhaseFlipNoise	
qpp::QubitDepolarizingNoise	
qpp::QubitPhaseFlipNoise	
qpp::QuditDepolarizingNoise	
qpp::NoiseType	56
qpp::internal::Singleton< T >	
qpp::internal::Singleton < const Codes >	1 5
qpp::Codes	39
qpp::internal::Singleton < const Gates >	
qpp::Gates	
qpp::internal::Singleton < const Init >	
qpp::lnit	
qpp::internal::Singleton < const States >	
qpp::States	
$qpp::internal::Singleton < Random Devices > \dots $	
qpp::RandomDevices	1 2
qpp::QEngine::state	50

3.1 Class Hierarchy 7

qpp::NoiseType::StateDependent	353
qpp::NoiseType::StateIndependent	353
true_type	
$qpp::is_complex < std::complex < T >> \ \ldots $	212
qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval< T	
>().end()), decltype(*(std::declya < T >().begin()))>>	214

8 Hierarchical Index

Chapter 4

Class Index

4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

qpp::Bit_circuit
Classical reversible circuit simulator
qpp::Codes
Const Singleton class that defines quantum error correcting codes
qpp::exception::CustomException
Custom exception
qpp::exception::DimsInvalid
Invalid dimension(s) exception
qpp::exception::DimsMismatchCvector
Dimension(s) mismatch column vector size exception
qpp::exception::DimsMismatchMatrix
Dimension(s) mismatch matrix size exception
qpp::exception::DimsMismatchRvector
Dimension(s) mismatch row vector size exception
qpp::exception::DimsMismatchVector
Dimension(s) mismatch vector size exception
qpp::exception::DimsNotEqual
Dimensions not equal exception
qpp::internal::Display_Impl
qpp::exception::Duplicates
System (e.g. std::vector) has duplicates exception
qpp::Dynamic_bitset
Dynamic bitset class, allows the specification of the number of bits at runtime
qpp::internal::EqualEigen
Functor for comparing Eigen expressions for equality
qpp::internal::EqualSameSizeStringDits
Functor for comparing strings of numbers of equal sizes in lexicographical order. Establishes a
strict weak ordering relation
qpp::exception::Exception
Base class for generating Quantum++ custom exceptions
qpp::Gates
Const Singleton class that implements most commonly used gates
qpp::QCircuit::GateStep
One step consisting only of gates/operators in the circuit
qpp::internal::HashEigen
Functor for hashing Eigen expressions

10 Class Index

qpp::IDisplay	
Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream@192	& os) const
qpp::IJSON	
Abstract class (interface) that mandates the definition of very basic JSON serialization support	194
qpp::ILayout	
Mandatory interface for layouts	195
qpp::Init	
Const Singleton class that performs additional initializations/cleanups	198
qpp::exception::InvalidIterator	
Invalid iterator	200
qpp::internal::IOManipEigen	202
qpp::internal::IOManipPointer< PointerType >	204
qpp::internal::IOManipRange < InputIterator >	208
qpp::is_complex< T >	
Checks whether the type is a complex type	211
qpp::is_complex< std::complex< T >>	
Checks whether the type is a complex number type, specialization for complex types	212
qpp::is_iterable< T, typename >	
Checks whether <i>T</i> is compatible with an STL-like iterable container	213
qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval< T >().end()), decltype(std::de	ecltype(*(std::declval<
Checks whether <i>T</i> is compatible with an STL-like iterable container, specialization for STL-like	
iterable containers	214
qpp::is_matrix_expression< Derived >	
Checks whether the type is an Eigen matrix expression	216
qpp::QCircuit::iterator	
Quantum circuit bound-checking (safe) iterator	217
qpp::Lattice	
N-dimensional orthogonal lattice coordinate system	222
qpp::make_void < Ts >	
Helper for qpp::to_void<> alias template	227
qpp::exception::MatrixMismatchSubsys	
Matrix mismatch subsystems exception	228
qpp::exception::MatrixNotCvector	
Matrix is not a column vector exception	230
qpp::exception::MatrixNotRvector	
Matrix is not a row vector exception	232
qpp::exception::MatrixNotSquare	
Matrix is not square exception	234
qpp::exception::MatrixNotSquareNorCvector	
Matrix is not square nor column vector exception	236
qpp::exception::MatrixNotSquareNorRvector	
Matrix is not square nor row vector exception	238
qpp::exception::MatrixNotSquareNorVector	
Matrix is not square nor vector exception	240
qpp::exception::MatrixNotVector	
	242
qpp::QCircuit::MeasureStep	
One step consisting only of measurements in the circuit	244
qpp::exception::NoCodeword	
Codeword does not exist exception	246
qpp::NoiseBase< T >	•
Base class for all noise models, derive your particular noise model	248
qpp::NoiseType	5
Contains template tags used to specify the noise type	256
qpp::exception::NotBipartite	
Not bi-partite exception	256

4.1 Class List

qpp::exception::NotImplemented	
Code not yet implemented	258
qpp::exception::NotQubitCvector	200
Column vector is not 2 x 1 exception	260
qpp::exception::NotQubitMatrix	
Matrix is not 2 x 2 exception	262
qpp::exception::NotQubitRvector	202
Row vector is not 1 x 2 exception	264
qpp::exception::NotQubitSubsys	20-
Subsystems are not qubits exception	266
qpp::exception::NotQubitVector	200
	260
Vector is not 2 x 1 nor 1 x 2 exception	268
qpp::exception::OutOfRange	070
Argument out of range exception	270
qpp::exception::PermInvalid	070
Invalid permutation exception	272
qpp::exception::PermMismatchDims	07
Permutation mismatch dimensions exception	274
qpp::QCircuit	
Quantum circuit description	277
qpp::QEngine	
Quantum circuit engine, executes qpp::QCircuit	314
qpp::QNoisyEngine < NoiseModel >	
Noisy quantum circuit engine, executes qpp::QCircuit	324
qpp::QubitAmplitudeDampingNoise	
Qubit amplitude damping noise, as described in Nielsen and Chuang	328
qpp::QubitBitFlipNoise	
Qubit bit flip noise	330
qpp::QubitBitPhaseFlipNoise	
Qubit bit-phase flip (dephasing) noise	331
qpp::QubitDepolarizingNoise	
Qubit depolarizing noise	333
qpp::QubitPhaseDampingNoise	
Qubit phase damping noise, as described in Nielsen and Chuang	334
qpp::QubitPhaseFlipNoise	
Qubit phase flip (dephasing) noise	336
qpp::exception::QuditAlreadyMeasured	
Qudit was already measured exception	337
qpp::QuditDepolarizingNoise	
Qudit depolarizing noise	339
qpp::RandomDevices	
Singleton class that manages the source of randomness in the library	342
qpp::internal::Singleton< T >	
Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously	
recurring template pattern)	345
qpp::exception::SizeMismatch	
Size mismatch exception	348
qpp::QEngine::state_	
Current state of the engine	350
qpp::NoiseType::StateDependent	
Template tag, used whenever the noise is state-dependent	353
qpp::NoiseType::StateIndependent	
Template tag, used whenever the noise is state-independent	353
qpp::States	
Const Singleton class that implements most commonly used states	353
qpp::exception::SubsysMismatchDims	
Subsystems mismatch dimensions exception	363
•	

12 Class Index

qpp::Timer< T, CLOCK_T >	
Chronometer	365
qpp::exception::TypeMismatch	
Type mismatch exception	369
qpp::exception::UndefinedType	
Not defined for this type exception	371
qpp::exception::Unknown	
Unknown exception	373
qpp::QCircuit::iterator::value_type_	
Value type class for qpp::QCircuit::iterator	375
qpp::exception::ZeroSize	
Object has zero size exception	379

Chapter 5

File Index

5.1 File List

Here is a list of all files with brief descriptions:

constants.h	
Constants	93
entanglement.h	
Entanglement functions	94
entropies.h	
Entropy functions	96
functions.h	
Generic quantum computing functions	97
input_output.h	
Input/output functions)2
instruments.h	
Measurement functions)3
number_theory.h	
Number theory functions)9
operations.h	
Quantum operation functions	11
qpp.h	
Quantum++ main header file, includes all other necessary headers	13
random.h	
Randomness-related functions	15
statistics.h	
Statistics functions	16
traits.h	
Type traits	17
Type aliases 41	40
classes/codes.h	19
Quantum error correcting codes	מפ
	J
classes/exception.h Exceptions	22
classes/gates.h	٥
Quantum gates	2F
classes/idisplay.h	,,
Display interface via the non-virtual interface (NVI) and very basic JSON serialization support	
interface	36

14 File Index

classes/init.h
Initialization
classes/layouts.h
Various physical qudit layouts, all must implement the interface ILayout
classes/noise.h
Noise models
classes/random_devices.h
Random devices
classes/reversible.h
Support for classical reversible circuits
classes/states.h
Quantum states
classes/timer.h
Timing
classes/circuits/circuits.h
Qudit quantum circuits
classes/circuits/engines.h
Qudit quantum engines
experimental/experimental.h
Experimental/test functions/classes
internal/util.h
Internal utility functions
internal/classes/iomanip.h
Input/output manipulators
internal/classes/singleton.h
Singleton pattern via CRTP
MATLAB/matlab.h
Input/output interfacing with MATLAB 40

Chapter 6

Namespace Documentation

6.1 qpp Namespace Reference

Quantum++ main namespace.

Namespaces

· exception

Quantum++ exception hierarchy namespace.

· experimental

Experimental/test functions/classes, do not use or modify.

internal

Internal utility functions, do not use them directly or modify them.

literals

Classes

• class Bit_circuit

Classical reversible circuit simulator.

• class Codes

const Singleton class that defines quantum error correcting codes

class Dynamic_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime.

· class Gates

const Singleton class that implements most commonly used gates

class IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

class IJSON

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

class ILayout

Mandatory interface for layouts.

· class Init

const Singleton class that performs additional initializations/cleanups

struct is_complex

Checks whether the type is a complex type.

struct is_complex< std::complex< T >>

Checks whether the type is a complex number type, specialization for complex types.

• struct is_iterable

Checks whether T is compatible with an STL-like iterable container.

• struct is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(*(std::declval < T >().end()), decltype(*(std::declval < T >().end()), decltype(std::declval < T >().end()), decltype(*(std::declval < T >().end()), decltype(*(std

Checks whether T is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

• struct is_matrix_expression

Checks whether the type is an Eigen matrix expression.

· class Lattice

N-dimensional orthogonal lattice coordinate system.

· struct make_void

Helper for qpp::to_void<> alias template.

· class NoiseBase

Base class for all noise models, derive your particular noise model.

class NoiseType

Contains template tags used to specify the noise type.

· class QCircuit

Quantum circuit description.

· class QEngine

Quantum circuit engine, executes qpp::QCircuit.

class QNoisyEngine

Noisy quantum circuit engine, executes qpp::QCircuit.

· class QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

· class QubitBitFlipNoise

Qubit bit flip noise.

· class QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

· class QubitDepolarizingNoise

Qubit depolarizing noise.

class QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

· class QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

· class QuditDepolarizingNoise

Qudit depolarizing noise.

· class RandomDevices

Singleton class that manages the source of randomness in the library.

· class States

const Singleton class that implements most commonly used states

class Timer

Chronometer.

• template<typename... Ts>

Typedefs

```
using to_void = typename make_void < Ts... >::type
          Alias template that implements the proposal for void_t.
    • using idx = std::size t
          Non-negative integer index, make sure you use an unsigned type.
    • using bigint = long long int
          Big integer.
    using cplx = std::complex< double >
          Complex number in double precision.
    using ket = Eigen::VectorXcd
          Complex (double precision) dynamic Eigen column vector.

    using bra = Eigen::RowVectorXcd

          Complex (double precision) dynamic Eigen row vector.
    • using cmat = Eigen::MatrixXcd
          Complex (double precision) dynamic Eigen matrix.
    using dmat = Eigen::MatrixXd
          Real (double precision) dynamic Eigen matrix.
    template<typename Scalar >
      using dyn mat = Eigen::Matrix < Scalar, Eigen::Dynamic, Eigen::Dynamic >
          Dynamic Eigen matrix over the field specified by Scalar.
    template<typename Scalar >
      using dyn_col_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 >
          Dynamic Eigen column vector over the field specified by Scalar.

    template<typename Scalar >

      using dyn_row_vect = Eigen::Matrix < Scalar, 1, Eigen::Dynamic >
          Dynamic Eigen row vector over the field specified by Scalar.
Enumerations
    enum { RES, PROB, ST }
          Constants to be used by std::get<> on the result of qpp::measure(), qpp_measure_seq() etc.
Functions

    cplx omega (idx D)

          D-th root of unity.

    template<typename Derived >

      dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx >
      &dims)
          Schmidt coefficients of the bi-partite pure state A.
    • template<typename Derived >
      dyn col vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2)
          Schmidt coefficients of the bi-partite pure state A.
```

cmat schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)

cmat schmidtA (const Eigen::MatrixBase< Derived > &A, idx d=2)

template<typename Derived >

template < typename Derived >

Schmidt basis on Alice side.

Schmidt basis on Alice side.

```
• template<typename Derived >
  cmat schmidtB (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &dims)
      Schmidt basis on Bob side.

    template < typename Derived >

  cmat schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Bob side.
\bullet \ \ {\it template}{<} {\it typename Derived} >
  std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx >
  &dims)
     Schmidt probabilities of the bi-partite pure state A.

    template<typename Derived >

  std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt probabilities of the bi-partite pure state A.
• template<typename Derived >
  double entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Entanglement of the bi-partite pure state A.

    template<typename Derived >

  double entanglement (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Entanglement of the bi-partite pure state A.

    template<typename Derived >

  double gconcurrence (const Eigen::MatrixBase< Derived > &A)
      G-concurrence of the bi-partite pure state A.

    template<typename Derived >

  double negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Negativity of the bi-partite mixed state A.

    template<typename Derived >

  double negativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Negativity of the bi-partite mixed state A.

    template<typename Derived >

  double lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double concurrence (const Eigen::MatrixBase< Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.
• template<typename Derived >
  double entropy (const Eigen::MatrixBase< Derived > &A)
      von-Neumann entropy of the density matrix A

    double entropy (const std::vector< double > &prob)

      Shannon entropy of the probability distribution prob.

    template<typename Derived >

  double renyi (const Eigen::MatrixBase< Derived > &A, double alpha)
      Renyi- \alpha entropy of the density matrix A, for \alpha \geq 0.

    double renyi (const std::vector< double > &prob, double alpha)

      Renyi- \alpha entropy of the probability distribution prob, for \alpha \geq 0.

    template<typename Derived >

  double tsallis (const Eigen::MatrixBase< Derived > &A, double q)
      Tsallis- q entropy of the density matrix A, for q \geq 0.

    double tsallis (const std::vector< double > &prob, double q)
```

Tsallis- q entropy of the probability distribution prob, for q > 0.

```
• template<typename Derived >
  double qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx > &subsysB, const std::vector<math>< idx > &dims)
     Quantum mutual information between 2 subsystems of a composite system.

    template<typename Derived >

  double qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector < idx > &subsysB, idx d=2)
     Quantum mutual information between 2 subsystems of a composite system.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > transpose (const Eigen::MatrixBase< Derived > &A)
     Transpose.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > conjugate (const Eigen::MatrixBase< Derived > &A)
     Complex conjugate.

    template < typename Derived >

  dyn_mat< typename Derived::Scalar > adjoint (const Eigen::MatrixBase< Derived > &A)
     Adjoint.
• template<typename Derived >
  dyn mat< typename Derived::Scalar > inverse (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  Derived::Scalar trace (const Eigen::MatrixBase< Derived > &A)
     Trace.

    template<typename Derived >

  Derived::Scalar det (const Eigen::MatrixBase< Derived > &A)
     Determinant.

    template<typename Derived >

  Derived::Scalar logdet (const Eigen::MatrixBase< Derived > &A)
     Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar sum (const Eigen::MatrixBase< Derived > &A)
     Element-wise sum of A.

    template<typename Derived >

  Derived::Scalar prod (const Eigen::MatrixBase< Derived > &A)
     Element-wise product of A.
• template<typename Derived >
  double norm (const Eigen::MatrixBase< Derived > &A)
     Frobenius norm.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > normalize (const Eigen::MatrixBase< Derived > &A)
     Normalizes state vector (column or row vector) or density matrix.

    template < typename Derived >

  std::pair < dyn_col_vect < cplx >, cmat > eig (const Eigen::MatrixBase < Derived > &A)
     Full eigen decomposition.

    template<typename Derived >

  dyn_col_vect< cplx > evals (const Eigen::MatrixBase< Derived > &A)
     Eigenvalues.
• template<typename Derived >
  cmat evects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors.
• template<typename Derived >
  std::pair< dyn_col_vect< double >, cmat > heig (const Eigen::MatrixBase< Derived > &A)
```

Full eigen decomposition of Hermitian expression.

Functor.

```
• template<typename Derived >
  dyn_col_vect< double > hevals (const Eigen::MatrixBase< Derived > &A)
     Hermitian eigenvalues.
ullet template<typename Derived >
  cmat hevects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors of Hermitian matrix.

    template<typename Derived >

  \verb|std::tuple| < \verb|cmat|, \verb|dyn_col_vect| < \verb|double| >, \verb|cmat| > \verb|svd| (const Eigen::MatrixBase| < Derived| > \&A) \\
     Full singular value decomposition.

    template<typename Derived >

  dyn_col_vect< double > svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.

    template<typename Derived >

  cmat svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.

    template < typename Derived >

  cmat svdV (const Eigen::MatrixBase< Derived > &A)
      Right singular vectors.
• template<typename Derived >
  cmat funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)

    template<typename Derived >

  cmat sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.

    template<typename Derived >

  cmat absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.

    template<typename Derived >

  cmat expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.
• template<typename Derived >
  cmat logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.

    template<typename Derived >

  cmat sinm (const Eigen::MatrixBase< Derived > &A)
• template<typename Derived >
  cmat cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.

    template<typename Derived >

  cmat spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > powm (const Eigen::MatrixBase< Derived > &A, idx n)
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

    template < typename Derived >

  double schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn mat< OutputScalar > cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const type-
  name Derived::Scalar &))
```

```
• template<typename T >
  dyn_mat< typename T::Scalar > kron (const T &head)
     Kronecker product.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > kron (const T &head, const Args &... tail)
     Kronecker product.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > kron (const std::vector< Derived > &As)
     Kronecker product.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > kron (const std::initializer list< Derived > &As)
     Kronecker product.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Kronecker power.
• template<typename T >
  dyn mat< typename T::Scalar > dirsum (const T &head)
template<typename T, typename... Args>
  dyn_mat< typename T::Scalar > dirsum (const T &head, const Args &... tail)
     Direct sum.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > dirsum (const std::vector< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > dirsum (const std::initializer_list< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > reshape (const Eigen::MatrixBase< Derived > &A, idx rows, idx
  cols)
     Reshape.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > comm (const Eigen::MatrixBase< Derived1 > &A, const Eigen::⊷
  MatrixBase< Derived2 > &B)
     Commutator.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > prj (const Eigen::MatrixBase< Derived > &A)
     Proiector.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > grams (const std::vector< Derived > &As)
     Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > grams (const std::initializer_list< Derived > &As)
     Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > grams (const Eigen::MatrixBase< Derived > &A)
```

Gram-Schmidt orthogonalization.

std::vector< idx > n2multiidx (idx n, const std::vector< idx > &dims)

Non-negative integer index to multi-index.

idx multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

Multi-index to non-negative integer index.

ket mket (const std::vector< idx > &mask, const std::vector< idx > &dims)

Multi-partite qudit ket.

ket mket (const std::vector< idx > &mask, idx d=2)

Multi-partite qudit ket.

cmat mprj (const std::vector < idx > &mask, const std::vector < idx > &dims)

Projector onto multi-partite qudit ket.

cmat mprj (const std::vector < idx > &mask, idx d=2)

Projector onto multi-partite qudit ket.

• template<typename InputIterator >

std::vector< double > abssq (InputIterator first, InputIterator last)

Computes the absolute values squared of an STL-like range of complex numbers.

template<typename Container >

std::vector< double > abssq (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Computes the absolute values squared of an STL-like container.

template<typename Derived >

```
std::vector< double > abssq (const Eigen::MatrixBase< Derived > &A)
```

Computes the absolute values squared of an Eigen expression.

template<typename InputIterator >

std::iterator_traits< InputIterator >::value_type sum (InputIterator first, InputIterator last)

Element-wise sum of an STL-like range.

template<typename Container >

Container::value_type sum (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

std::iterator traits< InputIterator >::value type prod (InputIterator first, InputIterator last)

Element-wise product of an STL-like range.

• template<typename Container >

Container::value_type prod (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Element-wise product of the elements of an STL-like container.

ullet template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > rho2pure (const Eigen::MatrixBase< Derived > &A)
```

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

std::vector< idx > complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

template<typename Derived >

```
std::vector< double > rho2bloch (const Eigen::MatrixBase< Derived > &A)
```

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

template<typename Derived >

```
std::size_t hash_eigen (const Eigen::MatrixBase< Derived > &A, std::size_t seed=0)
```

Computes the hash of en Eigen matrix/vector/expression.

template<typename Derived >

internal::IOManipEigen disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)

Eigen expression ostream manipulator.

• internal::IOManipEigen disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

• template<typename InputIterator >

internal::IOManipRange < InputIterator > disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)

Range ostream manipulator.

template<typename Container >

internal::IOManipRange< typename Container::const_iterator > disp (const Container &c, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop, typename std ::enable_if< is_iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

• template<typename PointerType >

internal::IOManipPointer< PointerType > disp (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)

C-style pointer ostream manipulator.

template<typename Derived >

void save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

template<typename Derived >

dyn_mat< typename Derived::Scalar > load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)

Generalized inner product.

• template<typename Derived >

dyn_col_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

template<typename Derived >

 $std::tuple < idx, std::vector < double >, std::vector < cmat > > measure (const Eigen::MatrixBase < Derived > &A, const std::initializer_list < cmat > &Ks)$

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple < idx, std::vector < double >, std::vector < cmat > > measure (const Eigen::MatrixBase < Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

template<typename Derived >

```
std::tuple < idx, std::vector < cmat >> measure (const Eigen::MatrixBase < Derived > &A, const std::vector < cmat > &Ks, const std::vector < idx > &target, const std::vector < idx > &dims)\\
```

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

 $std::tuple < idx, std::vector < cmat >> measure (const Eigen::MatrixBase < Derived > &A, const std::initializer_list < cmat > &Ks, const std::vector < idx > &target, const std::vector < idx > &dims)\\$

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple < idx, std::vector < double >, std::vector < cmat > > measure (const Eigen::MatrixBase < Derived > &A, const std::vector < cmat > &Ks, const std::vector < idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

ullet template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

template < typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template<typename Derived >

std::tuple< std::vector< idx >, double, cmat > measure_seq (const Eigen::MatrixBase< Derived > &A, std::vector< idx > target, idx d=2)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< cplx > >::type loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

 $\bullet \ \ \text{template}{<} \text{typename Derived} >$

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::

Scalar > >::type loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

std::vector< int > x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

bigint gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

bigint lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

• std::vector< idx> invperm (const std::vector< idx> &perm)

Inverse permutation.

std::vector< idx > compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

std::vector< bigint > factors (bigint a)

Prime factor decomposition.

• bigint modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

bigint modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple < bigint, bigint, bigint > egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint modiny (bigint a, bigint p)

Modular inverse of a mod p.

• bool isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

bigint randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

- std::vector < std::pair < int, int > > convergents (const std::vector < int > &cf)

Convergents.

std::vector< std::pair< int, int > > convergents (double x, idx N)

Convergents.

template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, const
std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, idx
d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen \leftrightarrow ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)
```

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

• template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, const std::vector< idx > &dims)
```

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

• template<typename Derived >

```
\begin{array}{l} \textbf{cmat apply (const Eigen::} MatrixBase < Derived > \&A, const std::vector < \textbf{cmat} > \&Ks, const std::vector < \textbf{idx} \\ > \&target, \textbf{idx} \ d=2) \end{array}
```

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat kraus2super (const std::vector< cmat > &Ks)

Superoperator matrix.

cmat kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector< cmat > choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

template<typename Derived >

 $dyn_mat< typename Derived::Scalar > ptrace1 (const Eigen::MatrixBase< Derived > &A, const std <math>\leftarrow ::vector < idx > &dims)$

Partial trace.

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

dyn_mat< typename Derived::Scalar > ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, const std↔ ::vector< idx > &dims)

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector<
idx > &target, const std::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector<
idx > &target, idx d=2)

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > ptranspose (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, const std::vector< idx > &dims)

Partial transpose.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptranspose (const Eigen::MatrixBase< Derived > &A, const std ← ::vector < idx > &target, idx d=2)

Partial transpose.

 $\bullet \;\; {\sf template}{<} {\sf typename \; Derived} >$

Subsystem permutation.

 $\bullet \ \ {\sf template}{<} {\sf typename \ Derived} >$

dyn_mat< typename Derived::Scalar > syspermute (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &perm, idx d=2)

Subsystem permutation.

template<typename Derived >

dyn_mat< typename Derived::Scalar > applyQFT (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2, bool swap=true)

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

dyn_col_vect< typename Derived::Scalar > TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Qudit quantum Fourier transform.

• double rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

bigint rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx randidx (idx a=std::numeric limits < idx >::min(), idx b=std::numeric limits < idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

• template<typename Derived >

Derived rand (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double a QPP_UNUSED_=0, double b QPP_UNUSED =1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

template<>

dmat rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

template<>

cmat rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived randn (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double mean QPP_UNUSED_=0, double sigma QPP_UNUSED_=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<

dmat randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

template<>

cmat randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

double randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

• cmat randU (idx D=2)

Generates a random unitary matrix.

· cmat randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector < cmat > randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat randH (idx D=2)

Generates a random Hermitian matrix.

ket randket (idx D=2)

Generates a random normalized ket (pure state vector)

cmat randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.

std::vector< double > uniform (idx N)

Uniform probability distribution vector.

std::vector< double > marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > marginalY (const dmat &probXY)

Marginal distribution.

• template<typename Container >

double avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Average.

• template<typename Container >

double cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Covariance.

• template<typename Container >

double var (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable<
Container >::value >::type *=nullptr)

Variance.

template<typename Container >

double sigma (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Standard deviation.

• template<typename Container >

double cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Correlation.

Variables

• constexpr double chop = 1e-16

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

• constexpr idx maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

• constexpr double pi = 3.141592653589793238462643383279502884

 π

• constexpr double ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

constexpr double infty = std::numeric_limits<double>::max()

Used to denote infinity in double precision.

6.1.1 Detailed Description

Quantum++ main namespace.

6.1.2 Typedef Documentation

```
6.1.2.1 bigint
```

```
using qpp::bigint = typedef long long int
```

Big integer.

6.1.2.2 bra

```
using qpp::bra = typedef Eigen::RowVectorXcd
```

Complex (double precision) dynamic Eigen row vector.

6.1.2.3 cmat

```
using qpp::cmat = typedef Eigen::MatrixXcd
```

Complex (double precision) dynamic Eigen matrix.

6.1.2.4 cplx

```
using qpp::cplx = typedef std::complex<double>
```

Complex number in double precision.

6.1.2.5 dmat

```
using qpp::dmat = typedef Eigen::MatrixXd
```

Real (double precision) dynamic Eigen matrix.

6.1.2.6 dyn_col_vect

```
template<typename Scalar >
using qpp::dyn_col_vect = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, 1>
```

Dynamic Eigen column vector over the field specified by Scalar.

Example:

```
// type of colvect is Eigen::Matrix<float, Eigen::Dynamic, 1>
dyn_col_vect<float> colvect(2);
```

```
6.1.2.7 dyn_mat
```

```
template<typename Scalar >
using qpp::dyn_mat = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, Eigen::Dynamic>
```

Dynamic Eigen matrix over the field specified by Scalar.

Example:

```
// type of mat is Eigen::Matrix<float, Eigen::Dynamic, Eigen::Dynamic>
dyn_mat<float> mat(2, 3);
```

6.1.2.8 dyn_row_vect

```
template<typename Scalar >
using qpp::dyn_row_vect = typedef Eigen::Matrix<Scalar, 1, Eigen::Dynamic>
```

Dynamic Eigen row vector over the field specified by Scalar.

Example:

```
// type of rowvect is Eigen::Matrix<float, 1, Eigen::Dynamic>
dyn_row_vect<float> rowvect(3);
```

6.1.2.9 idx

```
using qpp::idx = typedef std::size_t
```

Non-negative integer index, make sure you use an unsigned type.

6.1.2.10 ket

```
using qpp::ket = typedef Eigen::VectorXcd
```

Complex (double precision) dynamic Eigen column vector.

6.1.2.11 to_void

```
template<typename... Ts>
using qpp::to_void = typedef typename make_void<Ts...>::type
```

Alias template that implements the proposal for $void_t$.

See also

```
http://www.open-std.org/jtc1/sc22/wg21/docs/papers/2014/n3911
```

6.1.3 Enumeration Type Documentation

6.1.3.1 anonymous enum

```
anonymous enum
```

Constants to be used by std::get<> on the result of qpp::measure(), qpp_measure_seq() etc.

Enumerator

RES	Measurement result(s)
PROB	Probabilit(y)/(ies)
ST	Output state(s)

6.1.4 Function Documentation

6.1.4.1 absm()

Matrix absolute value.

Parameters

```
A Eigen expression
```

Returns

Matrix absolute value of A

6.1.4.2 abssq() [1/3]

Computes the absolute values squared of an STL-like range of complex numbers.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Real vector consisting of the range absolute values squared

Computes the absolute values squared of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Real vector consisting of the container's absolute values squared

Computes the absolute values squared of an Eigen expression.

Parameters

```
A Eigen expression
```

Returns

Real vector consisting of the absolute values squared

6.1.4.5 adjoint()

Adjoint.

```
A Eigen expression
```

Adjoint (Hermitian conjugate) of A, as a dynamic matrix over the same scalar field as A

6.1.4.6 anticomm()

Anti-commutator.

See also

qpp::comm()

Anti-commutator $\{A,B\}=AB+BA$. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
В	Eigen expression

Returns

Anti-commutator AB + BA, as a dynamic matrix over the same scalar field as A

6.1.4.7 apply() [1/5]

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

state	Eigen expression
Α	Eigen expression
catarget by Subsection indexes where the gate A is applied	
dims	Dimensions of the multi-partite system

Gate A applied to the part target of state

```
6.1.4.8 apply() [2/5]
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

Returns

Gate A applied to the part target of state

```
6.1.4.9 apply() [3/5]
```

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

Α	Eigen expression	
Ks	Set of Kraus operators	

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*.

Parameters

Α	Eigen expression	
Ks	Set of Kraus operators	
target	Subsystem indexes where the Kraus operators Ks are applied	
dims Dimensions of the multi-partite system		

Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*.

Α	Eigen expression	
Ks	Set of Kraus operators	
target	Subsystem indexes where the Kraus operators Ks are applied	
d	Subsystem dimensions	

Output density matrix after the action of the channel

6.1.4.12 applyCTRL() [1/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate A must match the dimension of *target*. Also, all control subsystems in *ctrl* must have the same dimension.

Parameters

state	Eigen expression	
Α	Eigen expression	
ctrl	Control subsystem indexes	
target	Subsystem indexes where the gate A is applied	
dims	Dimensions of the multi-partite system	

Returns

CTRL-A gate applied to the part target of state

6.1.4.13 applyCTRL() [2/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression	
Α	Eigen expression	
ctrl	Control subsystem indexes	
target	Subsystem indexes where the gate A is applied	
d	Subsystem dimensions	

Returns

CTRL-A gate applied to the part target of state

6.1.4.14 applyQFT()

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

Parameters

Α	Eigen expression	
target	Subsystem indexes where the QFT is applied	
d	Subsystem dimensions	
swap	Swaps the qubits/qudits at the end (true by default)	

Returns

Qudit Quantum Fourier transform applied to the part target of A

6.1.4.15 applyTFQ()

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::applyTFQ (
```

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & target,
idx d = 2,
bool swap = true )
```

Applies the inverse (adjoint) qudit quantum Fourier transform to the part *target* of the multi-partite state vector or density matrix *A*.

Parameters

Α	Eigen expression	
target	Subsystem indexes where the TFQ is applied	
d	Subsystem dimensions	
swap	Swaps the qubits/qudits at the end (true by default)	

Returns

Inverse (adjoint) qudit Quantum Fourier transform applied to the part target of A

6.1.4.16 avg()

Average.

Parameters

pro	b	Real probability vector representing the probability distribution of X
X		Real random variable values represented by an STL-like container

Returns

Average of X

6.1.4.17 bloch2rho()

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

See also

qpp::rho2bloch()

Parameters

r 3-dimensional real vector

Returns

Qubit density matrix

6.1.4.18 choi2kraus()

Orthogonal Kraus operators from Choi matrix.

See also

qpp::kraus2choi()

Extracts a set of orthogonal (under Hilbert-Schmidt operator norm) Kraus operators from the Choi matrix A

Note

The Kraus operators satisfy $Tr(K_i^\dagger K_j) = \delta_{ij}$ for all $i \neq j$

Parameters

A Choi matrix

Returns

Set of orthogonal Kraus operators

6.1.4.19 choi2super()

Converts Choi matrix to superoperator matrix.

See also

qpp::super2choi()

Parameters

```
A Choi matrix
```

Returns

Superoperator matrix

6.1.4.20 comm()

Commutator.

See also

qpp::anticomm()

Commutator [A, B] = AB - BA. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
В	Eigen expression

Returns

Commutator AB-BA, as a dynamic matrix over the same scalar field as ${\it A}$

6.1.4.21 complement()

```
std::vector<idx> qpp::complement (
    std::vector< idx > subsys,
    idx n ) [inline]
```

Constructs the complement of a subsystem vector.

subsys	Subsystem vector
n	Total number of systems

Complement of *subsys* with respect to the set $\{0, 1, \dots, n-1\}$

6.1.4.22 compperm()

Compose permutations.

Parameters

perm	Permutation
sigma	Permutation

Returns

Composition of the permutations $perm \circ sigma = perm(sigma)$

6.1.4.23 concurrence()

Wootters concurrence of the bi-partite qubit mixed state A.

Parameters

```
A Eigen expression
```

Returns

Wootters concurrence

6.1.4.24 conjugate()

Complex conjugate.

Parameters

A Eigen expression

Returns

Complex conjugate of A, as a dynamic matrix over the same scalar field as A

6.1.4.25 contfrac2x()

```
double qpp::contfrac2x ( const std::vector< int > & cf, idx N = idx(-1) ) [inline]
```

Real representation of a simple continued fraction.

See also

qpp::x2contfrac()

Note

If N is greater than the size of cf (by default it is), then all terms in cf are considered.

Parameters

cf	Integer vector containing the simple continued fraction expansion
Ν	Number of terms considered in the continued fraction expansion.

Returns

Real representation of the simple continued fraction

6.1.4.26 convergents() [1/2]

```
std::vector<std::pair<int, int> > qpp::convergents ( const std::vector< int > & cf ) [inline]
```

Convergents.

See also

qpp::contfrac2x() and qpp::x2contfrac()

```
cf Continued fraction
```

Returns

Vector of convergents pairs (a_k, b_k) that approximate the number represented by the continued fraction

6.1.4.27 convergents() [2/2] std::vector<std::pair<int, int> > qpp::convergents (

idx N) [inline]

double x,

Convergents.

See also

```
qpp::contfrac2x() and qpp::x2contfrac()
```

Note

In the continued fraction expansion of x has less terms than N, then the series of convergents is truncated to the number of terms in the continued fraction expansion of x.

Parameters

	Χ	Real number
N Number of converge		Number of convergents.

Returns

Vector of convergents pairs (a_k, b_k) that approximate the number x

6.1.4.28 cor()

Correlation.

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels the rows, Y labels the columns)
Χ	Real random variable values represented by an STL-like container
Y	Real random variable values represented by an STL-like container

Returns

Correlation of X and Y

6.1.4.29 cosm()

Matrix cos.

Parameters

```
A Eigen expression
```

Returns

Matrix cosine of A

6.1.4.30 cov()

Covariance.

probXY	Real matrix representing the joint probability distribution of <i>X</i> and <i>Y</i> in lexicographical order (<i>X</i> labels the rows, <i>Y</i> labels the columns)	
Χ	Real random variable values represented by an STL-like container	
Υ	Real random variable values represented by an STL-like container	

Covariance of X and Y

6.1.4.31 cwise()

Functor.

Parameters

Α	Eigen expression
f	Pointer-to-function from scalars of A to OutputScalar

Returns

Component-wise f(A), as a dynamic matrix over the *OutputScalar* scalar field

6.1.4.32 det()

Determinant.

Parameters

```
A Eigen expression
```

Returns

Determinant of A, as a scalar over the same scalar field as A. Returns $\pm \infty$ when the determinant overflows/underflows.

Direct sum.

See also

qpp::dirsumpow()

Used to stop the recursion for the variadic template version of qpp::dirsum()

Parameters

```
head Eigen expression
```

Returns

Its argument head

6.1.4.34 dirsum() [2/4]

Direct sum.

See also

qpp::dirsumpow()

Parameters

	head	Eigen expression	
tail Variadic Eigen expression (zero or more param		Variadic Eigen expression (zero or more parameters)	

Returns

Direct sum of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.4.35 dirsum() [3/4]

Direct sum.

See also

qpp::dirsumpow()

As std::vector of Eigen expressions

Returns

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

See also

qpp::dirsumpow()

Parameters

As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}

Returns

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.4.37 dirsumpow()

Direct sum power.

See also

qpp::dirsum()

Α	Eigen expression	
n	Non-negative integer	

Returns

Direct sum of A with itself n times $A^{\oplus n}$, as a dynamic matrix over the same scalar field as A

Eigen expression ostream manipulator.

Parameters

Α	Eigen expression
chop Set to zero the elements smaller in absolute value than	

Returns

Instance of qpp::internal::IOManipEigen

Complex number ostream manipulator.

Parameters

Z	Complex number (or any other type implicitly cast-able to std::complex <double>)</double>	
chop	Set to zero the elements smaller in absolute value than chop	

Returns

Instance of qpp::internal::IOManipEigen

Range ostream manipulator.

Parameters

first	Iterator to the first element of the range	
last	Iterator to the last element of the range	
separator	Separator	
start	Left marking	
end Right marking		
chop	Set to zero the elements smaller in absolute value than chop	

Returns

Instance of qpp::internal::IOManipRange

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

С	Container	
separator Separator		
start	Left marking	
end Right marking		
chop	Set to zero the elements smaller in absolute value than chop	

Instance of qpp::internal::IOManipRange

C-style pointer ostream manipulator.

Parameters

р	Pointer to the first element	
N	Number of elements to be displayed	
separator	Separator	
start	Left marking	
end	Right marking	
chop Set to zero the elements smaller in absolute value that		

Returns

Instance of qpp::internal::IOManipPointer

6.1.4.43 egcd()

Extended greatest common divisor of two integers.

See also

qpp::gcd()

а	Integer
b	Integer

Tuple of: 1. Integer m, 2. Integer n, and 3. Non-negative integer gcd(a,b) such that ma + nb = gcd(a,b)

6.1.4.44 eig()

Full eigen decomposition.

See also

qpp::heig()

Parameters

```
A Eigen expression
```

Returns

Pair of: 1. Eigenvalues of A, as a complex dynamic column vector, and 2. Eigenvectors of A, as columns of a complex dynamic matrix

6.1.4.45 entanglement() [1/2]

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

qpp::entropy()

Α	A Eigen expression	
dims	Dimensions of the bi-partite system	

Entanglement, with the logarithm in base 2

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

qpp::entropy()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Entanglement, with the logarithm in base 2

von-Neumann entropy of the density matrix A

Parameters

```
A Eigen expression
```

Returns

von-Neumann entropy, with the logarithm in base 2

Shannon entropy of the probability distribution prob.

Parameters

```
prob Real probability vector
```

Returns

Shannon entropy, with the logarithm in base 2

6.1.4.49 evals()

Eigenvalues.

See also

qpp::hevals()

Parameters

```
A Eigen expression
```

Returns

Eigenvalues of A, as a complex dynamic column vector

6.1.4.50 evects()

Eigenvectors.

See also

qpp::hevects()

A Eigen expression

Returns

Eigenvectors of A, as columns of a complex dynamic matrix

6.1.4.51 expm()

Matrix exponential.

Parameters

A Eigen expression

Returns

Matrix exponential of A

6.1.4.52 factors()

Prime factor decomposition.

Note

Runs in $\mathcal{O}(\sqrt{n})$ time complexity

Parameters

a Integer different from 0, 1 or -1

Returns

Integer vector containing the factors

6.1.4.53 funm()

Functional calculus f(A)

Parameters

Α	Eigen expression
f	Pointer-to-function from complex to complex

Returns

f(A)

Greatest common divisor of two integers.

See also

```
qpp::lcm()
```

Parameters

а	Integer
b	Integer

Returns

Greatest common divisor of a and b

Greatest common divisor of a list of integers.

See also

```
qpp::lcm()
```

Parameters

```
as List of integers
```

Returns

Greatest common divisor of all numbers in as

6.1.4.56 gconcurrence()

G-concurrence of the bi-partite pure state A.

Note

Both local dimensions must be equal

Uses qpp::logdet() to avoid overflows

See also

```
qpp::logdet()
```

Parameters

```
A Eigen expression
```

Returns

G-concurrence

```
6.1.4.57 grams() [1/3]
```

Gram-Schmidt orthogonalization.

As std::vector of Eigen expressions as column vectors

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

Gram-Schmidt orthogonalization.

Parameters

As std::initializer_list of Eigen expressions as column vectors

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

Gram-Schmidt orthogonalization.

Parameters

A Eigen expression, the input vectors are the columns of A

Returns

Gram-Schmidt vectors of the columns of A, as columns of a dynamic matrix over the same scalar field as A

6.1.4.60 hash_eigen()

Computes the hash of en Eigen matrix/vector/expression.

Note

Code taken from boost::hash_combine(), see https://www.boost.org/doc/libs/1_69_← 0/doc/html/hash/reference.html#boost.hash_combine

Parameters

Α	Eigen expression
seed	Seed, 0 by default

Returns

Hash of its argument

6.1.4.61 heig()

Full eigen decomposition of Hermitian expression.

See also

qpp::eig()

Parameters

A Eigen expression

Returns

Pair of: 1. Eigenvalues of A, as a real dynamic column vector, and 2. Eigenvectors of A, as columns of a complex dynamic matrix

6.1.4.62 hevals()

Hermitian eigenvalues.

See also

qpp::evals()

Parameters

A Eigen expression

Returns

Eigenvalues of Hermitian A, as a real dynamic column vector

6.1.4.63 hevects()

Eigenvectors of Hermitian matrix.

See also

qpp::evects()

Parameters

A Eigen expression

Returns

Eigenvectors of Hermitian matrix A, as columns of a complex matrix

6.1.4.64 inverse()

Inverse.

```
A Eigen expression
```

Returns

Inverse of A, as a dynamic matrix over the same scalar field as A

6.1.4.65 invperm()

```
std::vector<idx> qpp::invperm ( const std::vector< idx > & perm ) [inline]
```

Inverse permutation.

Parameters

perm	Permutation
------	-------------

Returns

Inverse of the permutation perm

6.1.4.66 ip() [1/2]

Generalized inner product.

Parameters

phi	Column vector Eigen expression
psi	Column vector Eigen expression
subsys	Subsystem indexes over which phi is defined
dims	Dimensions of the multi-partite system

Returns

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

Generalized inner product.

Parameters

phi	Column vector Eigen expression
psi	Column vector Eigen expression
subsys	Subsystem indexes over which phi is defined
d	Subsystem dimensions

Returns

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

6.1.4.68 isprime()

```
bool qpp::isprime ( bigint p, idx k = 80 ) [inline]
```

Primality test based on the Miller-Rabin's algorithm.

Parameters

р	Integer different from 0, 1 or -1	
k	Number of iterations. The probability of a false positive is 2^{-k} .	

Returns

True if the number is (most-likely) prime, false otherwise

6.1.4.69 kraus2choi()

Choi matrix.

See also

qpp::choi2kraus()

Constructs the Choi matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|$, $|0\rangle\langle 1|$ etc.

Note

The superoperator matrix S and the Choi matrix C are related by $S_{ab,mn}=C_{ma,nb}$

Parameters

```
Ks Set of Kraus operators
```

Returns

Choi matrix

6.1.4.70 kraus2super()

Superoperator matrix.

Constructs the superoperator matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|$, $|0\rangle\langle 1|$ etc.

Parameters

```
Ks Set of Kraus operators
```

Returns

Superoperator matrix

Kronecker product.

|--|

qpp::kronpow()

Used to stop the recursion for the variadic template version of app::kron()

head Eigen expression	
-----------------------	--

Returns

Its argument head

Kronecker product.

See also

qpp::kronpow()

Parameters

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

Returns

Kronecker product of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Kronecker product.

See also

qpp::kronpow()

```
As std::vector of Eigen expressions
```

Returns

Kronecker product of all elements in *As*, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

See also

qpp::kronpow()

Parameters

```
As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}
```

Returns

Kronecker product of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.4.75 kronpow()

Kronecker power.

See also

qpp::kron()

Α	Eigen expression
n	Non-negative integer

Returns

Kronecker product of A with itself n times $A^{\otimes n}$, as a dynamic matrix over the same scalar field as A

Least common multiple of two integers.

See also

```
qpp::gcd()
```

Parameters

а	Integer
b	Integer

Returns

Least common multiple of a and b

Least common multiple of a list of integers.

See also

```
qpp::gcd()
```

ac	List of integers
as	

Least common multiple of all numbers in as

6.1.4.78 load()

Loads Eigen matrix from a binary file (internal format) in double precision.

See also

```
qpp::save()
```

The template parameter cannot be automatically deduced and must be explicitly provided, depending on the scalar field of the matrix that is being loaded.

Example:

```
// loads a previously saved Eigen dynamic complex matrix from "input.bin"
cmat mat = load<cmat>("input.bin");
```

Parameters

```
fname Output file name
```

6.1.4.79 loadMATLAB() [1/2]

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

```
qpp::saveMATLAB()
```

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen ket
// from the MATLAB file "input.mat"
ket psi = loadMATLABket>("input.mat");
```

Template Parameters

Derived C	omplex Eigen type
-----------	-------------------

Parameters

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be loaded

Returns

Eigen dynamic matrix

6.1.4.80 loadMATLAB() [2/2]

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

qpp::saveMATLAB()

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen dynamic double matrix // from the MATLAB file "input.mat" dmat mat = loadMATLAB
```

Template Parameters

Derived	Non-complex Eigen type
---------	------------------------

Parameters

ĺ	mat_file	MATALB .mat file
	var_name	Variable name in the .mat file representing the matrix to be loaded

Returns

Eigen dynamic matrix

6.1.4.81 logdet()

Logarithm of the determinant.

Useful when the determinant overflows/underflows

Parameters

```
A Eigen expression
```

Returns

Logarithm of the determinant of A, as a scalar over the same scalar field as A

6.1.4.82 logm()

Matrix logarithm.

Parameters

```
A Eigen expression
```

Returns

Matrix logarithm of A

6.1.4.83 lognegativity() [1/2]

Logarithmic negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
alian a	Disconnicuo of the bi secutite exetern
aims	Dimensions of the bi-partite system

Generated by Doxygen

Logarithmic negativity, with the logarithm in base 2

```
6.1.4.84 lognegativity() [2/2] template<typename Derived > double qpp::lognegativity ( const Eigen::MatrixBase< Derived > & A, idx d = 2)
```

Logarithmic negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Logarithmic negativity, with the logarithm in base 2

6.1.4.85 marginalX()

Marginal distribution.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels
	the rows, Y labels the columns)

Returns

Real vector consisting of the marginal distribution of X

6.1.4.86 marginalY()

Marginal distribution.

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels	1
	the rows, Y labels the columns)	

Returns

Real vector consisting of the marginal distribution of Y

Measures the state vector or density operator A using the set of Kraus operators Ks.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.4.88 measure() [2/9]

Measures the state vector or density matrix \boldsymbol{A} using the set of Kraus operators \boldsymbol{Ks} .

Α	Eigen expression
Ks	Set of Kraus operators

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

Parameters

Α	Eigen expression	
U	Unitary matrix whose columns represent the measurement basis vectors]

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.4.91 measure() [5/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.4.92 measure() [6/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.4.93 measure() [7/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.4.94 measure() [8/9]

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

See also

```
qpp::measure_seq()
```

Note

The dimension of V must match the dimension of target. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.4.95 measure() [9/9]

Measures the part *target* of the multi-partite state vector or density matrix *A* in the orthonormal basis or rank-1 projectors specified by the columns of the matrix *V*.

See also

```
qpp::measure_seq()
```

Note

The dimension of *V* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

```
template<typename Derived >
std::tuple<std::vector<idx>, double, cmat> qpp::meas
```

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

See also

qpp::measure()

6.1.4.96 measure_seq() [1/2]

Α	Eigen expression
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

See also

qpp::measure()

Parameters

Α	Eigen expression
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|\text{mask}\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

Parameters

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

Returns

Multi-partite qudit state vector, as a complex dynamic column vector

```
6.1.4.99 mket() [2/2] ket qpp::mket ( const std::vector< idx > & mask, idx d = 2) [inline]
```

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Multi-partite qudit state vector, as a complex dynamic column vector

6.1.4.100 modinv()

Modular inverse of a mod p.

See also

```
qpp::egcd()
```

Note

a and p must be co-prime

Parameters

а	Non-negative integer
р	Non-negative integer

Returns

```
Modular inverse a^{-1} \mod p
```

6.1.4.101 modmul()

```
bigint qpp::modmul (
          bigint a,
          bigint b,
          bigint p ) [inline]
```

Modular multiplication without overflow.

Computes $ab \bmod p$ without overflow

Parameters

а	Integer
b	Integer
р	Positive integer

Returns

 $ab \bmod p \text{ avoiding overflow}$

6.1.4.102 modpow()

Fast integer power modulo \emph{p} based on the SQUARE-AND-MULTIPLY algorithm.

Note

Uses qpp::modmul() that avoids overflows

Computes $a^n \mod p$

Parameters

а	Non-negative integer
n	Non-negative integer
р	Strictly positive integer

Returns

```
a^n \bmod p
```

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

Parameters

I	mask	std::vector of non-negative integers
(dims	Dimensions of the multi-partite system

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

```
6.1.4.104 mprj() [2/2] cmat qpp::mprj ( const std::vector< idx > \& mask, idx d = 2) [inline]
```

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

6.1.4.105 multiidx2n()

```
idx qpp::multiidx2n ( const \ std::vector < \ idx \ > \ \& \ midx, const \ std::vector < \ idx \ > \ \& \ dims \ ) \quad [inline]
```

Multi-index to non-negative integer index.

See also

```
qpp::n2multiidx()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

Parameters

m	idx	Multi-index
di	ims	Dimensions of the multi-partite system

Returns

Non-negative integer index

6.1.4.106 n2multiidx()

Non-negative integer index to multi-index.

See also

qpp::multiidx2n()

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

Parameters

n	Non-negative integer index
dims	Dimensions of the multi-partite system

Returns

Multi-index of the same size as dims

```
6.1.4.107 negativity() [1/2]
```

Negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Negativity

6.1.4.108 negativity() [2/2]

```
template<typename Derived > double qpp::negativity ( const Eigen::MatrixBase< Derived > & A, idx d = 2)
```

Negativity of the bi-partite mixed state A.

Α	Eigen expression
d	Subsystem dimensions

Negativity

6.1.4.109 norm()

Frobenius norm.

Parameters

```
A Eigen expression
```

Returns

Frobenius norm of A

6.1.4.110 normalize()

Normalizes state vector (column or row vector) or density matrix.

Parameters

```
A Eigen expression
```

Returns

Normalized state vector or density matrix

6.1.4.111 omega()

```
cplx qpp::omega (
        idx D ) [inline]
```

D-th root of unity.

```
D Non-negative integer
```

Returns

D-th root of unity $\exp(2\pi i/D)$

6.1.4.112 powm()

Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

See also

qpp::spectralpowm()

Explicitly multiplies the matrix A with itself n times. By convention $A^0 = I$.

Parameters

Α	Eigen expression
n	Non-negative integer

Returns

Matrix power A^n , as a dynamic matrix over the same scalar field as ${\it A}$

6.1.4.113 prj()

Projector.

Normalized projector onto state vector

Parameters

A Eigen expression

Projector onto the state vector *A*, or the matrix *Zero* if *A* has norm zero, as a dynamic matrix over the same scalar field as *A*

Element-wise product of A.

Parameters

```
A Eigen expression
```

Returns

Element-wise product of A, as a scalar over the same scalar field as A

Element-wise product of an STL-like range.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Element-wise product of the range, as a scalar over the same scalar field as the range

```
6.1.4.116 prod() [3/3]

template<typename Container >
Container::value_type qpp::prod (
```

```
const Container & c,
typename std::enable_if< is_iterable< Container >::value >::type * = nullptr )
```

Element-wise product of the elements of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Element-wise product of the elements of the container, as a scalar over the same scalar field as the container

Partial trace.

See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Returns

Partial trace $Tr_{subsys}(\cdot)$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

Partial trace.

See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

A Eigen expression	
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial trace $Tr_{subsys}(\cdot)$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.4.119 ptrace1() [1/2]

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_A(\cdot)$ over the first subsytem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.4.120 ptrace1() [2/2]

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::ptrace1 (
```

```
const Eigen::MatrixBase< Derived > & A, idx d = 2)
```

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_A(\cdot)$ over the first subsytem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.4.121 ptrace2() [1/2]

Partial trace.

See also

qpp::ptrace1()

Partial trace over the second subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_B(\cdot)$ over the second subsytem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.4.122 ptrace2() [2/2]

Partial trace.

See also

```
qpp::ptrace1()
```

Partial trace over the second subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_B(\cdot)$ over the second subsystem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.4.123 ptranspose() [1/2]

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.4.124 ptranspose() [2/2]

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.4.125 QFT()

Qudit quantum Fourier transform.

Parameters

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Qudit quantum Fourier transform applied on A

6.1.4.126 qmutualinfo() [1/2]

```
template<typename Derived >
double qpp::qmutualinfo (
```

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & subsysA,
const std::vector< idx > & subsysB,
const std::vector< idx > & dims )
```

Quantum mutual information between 2 subsystems of a composite system.

Parameters

Α	Eigen expression	
subsysA	Indexes of the first subsystem	
subsysB	Indexes of the second subsystem	
dims	Dimensions of the multi-partite system	

Returns

Mutual information between the 2 subsystems

6.1.4.127 qmutualinfo() [2/2]

Quantum mutual information between 2 subsystems of a composite system.

Parameters

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
d	Subsystem dimensions

Returns

Mutual information between the 2 subsystems

Generates a random real number uniformly distributed in the interval [a, b)

	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Returns

Random real number (double) uniformly distributed in the interval [a, b)

Generates a random big integer uniformly distributed in the interval [a, b].

Note

To avoid ambiguity with double qpp::rand(double, double) cast at least one of the arguments to qpp::bigint

Parameters

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

Returns

Random big integer uniformly distributed in the interval [a, b]

Generates a random matrix with entries uniformly distributed in the interval [a, b)

If complex, then both real and imaginary parts are uniformly distributed in [a, b)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries uniformly distributed in [-1,1)
dmat mat = rand<dmat>(3, 3, -1, 1);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Returns

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example

```
// generates a 3 x 3 random Eigen::MatrixXcd,
// with entries (both real and imaginary) uniformly distributed in [-1,1)
cmat mat = rand<cmat>(3, 3, -1, 1);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
Generated	bদ্ৰাপ্তাৰণীhe interval, does not belong to it

Random complex matrix

6.1.4.133 randH()

```
cmat qpp::randH (
    idx D = 2 ) [inline]
```

Generates a random Hermitian matrix.

Parameters

D Dimension of the Hilbert space

Returns

Random Hermitian matrix

6.1.4.134 randidx()

```
idx qpp::randidx (
        idx a = std::numeric_limits<idx>::min(),
        idx b = std::numeric_limits<idx>::max() ) [inline]
```

Generates a random index (idx) uniformly distributed in the interval [a, b].

Parameters

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

Returns

Random index (idx) uniformly distributed in the interval [a, b]

6.1.4.135 randket()

```
ket qpp::randket (
    idx D = 2 ) [inline]
```

Generates a random normalized ket (pure state vector)

D Dimension of the Hilbert space

Returns

Random normalized ket

6.1.4.136 randkraus()

```
std::vector<cmat> qpp::randkraus (
    idx N,
    idx D = 2) [inline]
```

Generates a set of random Kraus operators.

Note

The set of Kraus operators satisfy the closure condition $\sum_i K_i^\dagger K_i = I$

Parameters

Ν	Number of Kraus operators
D	Dimension of the Hilbert space

Returns

6.1.4.137 randn() [1/4]

Set of N Kraus operators satisfying the closure condition

```
template<typename Derived >
Derived qpp::randn (
    idx rows QPP_UNUSED_,
```

idx cols QPP_UNUSED_,

double mean QPP_UNUSED_ = 0,
double sigma QPP_UNUSED_ = 1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

If complex, then both real and imaginary parts are normally distributed in N(mean, sigma)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries normally distributed in N(0,2)
dmat mat = randn<dmat>(3, 3, 0, 2);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Returns

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd,
// with entries (both real and imaginary) normally distributed in N(0,2)
cmat mat = randn<cmat>(3, 3, 0, 2);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Random complex matrix

Generates a random real number (double) normally distributed in N(mean, sigma)

Parameters

mean	Mean
sigma	Standard deviation

Returns

Random real number normally distributed in N(mean, sigma)

6.1.4.141 randperm()

```
std::vector<idx> qpp::randperm (
    idx N ) [inline]
```

Generates a random uniformly distributed permutation.

Uses Knuth shuffle method (as implemented by std::shuffle), so that all permutations are equally probable

Parameters

```
N Size of the permutation
```

Returns

Random permutation of size N

6.1.4.142 randprime()

```
bigint b,
idx N = 1000) [inline]
```

Generates a random big prime uniformly distributed in the interval [a, b].

а	Beginning of the interval, belongs to it
b End of the	End of the interval, belongs to it
Ν	Maximum number of candidates

Returns

Random big integer uniformly distributed in the interval [a, b]

6.1.4.143 randprob()

```
std::vector<double> qpp::randprob (
    idx N ) [inline]
```

Generates a random probability vector uniformly distributed over the probability simplex.

Parameters

N Size of the probability vector

Returns

Random probability vector

6.1.4.144 randrho()

```
cmat qpp::randrho (
    idx D = 2) [inline]
```

Generates a random density matrix.

Parameters

D Dimension of the Hilbert space

Returns

Random density matrix

6.1.4.145 randU()

```
cmat qpp::randU (
    idx D = 2 ) [inline]
```

Generates a random unitary matrix.

Parameters

```
D Dimension of the Hilbert space
```

Returns

Random unitary

6.1.4.146 randV()

Generates a random isometry matrix.

Parameters

Din	Size of the input Hilbert space
Dout	Size of the output Hilbert space

Returns

Random isometry matrix

Renyi- α entropy of the density matrix ${\it A}$, for $\alpha \geq 0$.

Note

When lpha o 1 the Renyi entropy converges to the von-Neumann entropy, with the logarithm in base 2

Α	Eigen expression
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

Returns

Renyi- α entropy, with the logarithm in base 2

Renyi- α entropy of the probability distribution *prob*, for $\alpha \geq 0$.

Note

When $\alpha \to 1$ the Renyi entropy converges to the Shannon entropy, with the logarithm in base 2

Parameters

prob	Real probability vector
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

Returns

Renyi- α entropy, with the logarithm in base 2

6.1.4.149 reshape()

Reshape.

Uses column-major order when reshaping (same as MATLAB)

Α	Eigen expression
	Number of rows of the reshaped matrix
Genera CO/S	by Poxygen of columns of the reshaped matrix

Reshaped matrix with rows rows and cols columns, as a dynamic matrix over the same scalar field as A

6.1.4.150 rho2bloch()

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

See also

qpp::bloch2rho()

Note

It is implicitly assumed that the density matrix is Hermitian

Parameters

A Eigen expression

Returns

3-dimensional Bloch vector

6.1.4.151 rho2pure()

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

Note

No purity check is done, the input state A must have rank one, otherwise the function returns the first non-zero eigenvector of A

Parameters

A Eigen expression, assumed to be proportional to a projector onto a pure state, i.e. A is assumed to have rank one

The unique non-zero eigenvector of A (up to a phase), as a dynamic column vector over the same scalar field as A

6.1.4.152 save()

Saves Eigen expression to a binary file (internal format) in double precision.

See also

qpp::load()

Parameters

Α	Eigen expression	
fname	Output file name	

6.1.4.153 saveMATLAB() [1/2]

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

qpp::loadMATLAB()

Template Parameters

Complex	Eigen type
Complex	goypo

Α	Eigen expression over the complex field
---	---

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be saved
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details

6.1.4.154 saveMATLAB() [2/2]

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

qpp::loadMATLAB()

Template Parameters

igen type

Parameters

Α	Non-complex Eigen expression
mat_file	MATALB .mat file
var_name Variable name in the .mat file representing the mat	Variable name in the .mat file representing the matrix to be saved
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details

6.1.4.155 schatten()

Schatten matrix norm.

Α	Eigen expression
р	Real number, greater or equal to 1, use qpp::infty for $p=\infty$

Schatten-p matrix norm of A

Schmidt basis on Alice side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix ${\cal U}$ whose columns represent the Schmidt basis vectors on Alice side.

Schmidt basis on Alice side.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix U whose columns represent the Schmidt basis vectors on Alice side.

6.1.4.158 schmidtB() [1/2] template<typename Derived > cmat qpp::schmidtB (

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & dims )
```

Schmidt basis on Bob side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

Schmidt basis on Bob side.

idx d = 2)

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.4.161 schmidtcoeffs() [2/2]

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.4.162 schmidtprobs() [1/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.4.163 schmidtprobs() [2/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.4.164 sigma()

Standard deviation.

prob	Real probability vector representing the probability distribution of X
X	Real random variable values represented by an STL-like container

Returns

Standard deviation of X

6.1.4.165 sinm()

Matrix sin.

Parameters

A Eigen expression

Returns

Matrix sine of A

6.1.4.166 spectralpowm()

Matrix power.

See also

qpp::powm()

Uses the spectral decomposition of \emph{A} to compute the matrix power. By convention $\emph{A}^0 = \emph{I}$.

Α	Eigen expression
Z	Complex number

Matrix power A^z

6.1.4.167 sqrtm()

Matrix square root.

Parameters

```
A Eigen expression
```

Returns

Matrix square root of A

```
6.1.4.168 sum() [1/3]
```

Element-wise sum of A.

Parameters

```
A Eigen expression
```

Returns

Element-wise sum of A, as a scalar over the same scalar field as A

```
6.1.4.169 sum() [2/3]
```

Element-wise sum of an STL-like range.

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Element-wise sum of the range, as a scalar over the same scalar field as the range

Element-wise sum of the elements of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Element-wise sum of the elements of the container, as a scalar over the same scalar field as the container

6.1.4.171 super2choi()

Converts superoperator matrix to Choi matrix.

See also

qpp::choi2super()

Parameters

A Superoperator matrix

Choi matrix

6.1.4.172 svals()

Singular values.

Parameters

A Eigen expression

Returns

Singular values of A, ordered in decreasing order, as a real dynamic column vector

6.1.4.173 svd()

Full singular value decomposition.

Parameters

A Eigen expression

Returns

Tuple of: 1. Left sigular vectors of A, as columns of a complex dynamic matrix, 2. Singular values of A, ordered in decreasing order, as a real dynamic column vector, and 3. Right singular vectors of A, as columns of a complex dynamic matrix

6.1.4.174 svdU()

Left singular vectors.

```
A Eigen expression
```

Returns

Complex dynamic matrix, whose columns are the left singular vectors of A

6.1.4.175 svdV()

Right singular vectors.

Parameters

```
A Eigen expression
```

Returns

Complex dynamic matrix, whose columns are the right singular vectors of A

6.1.4.176 syspermute() [1/2]

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit *perm[i]* is permuted to the location *i*.

Α	Eigen expression
perm	Permutation
dims	Dimensions of the multi-partite system

Permuted system, as a dynamic matrix over the same scalar field as A

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit *perm[i]* is permuted to the location *i*.

Parameters

Α	Eigen expression
perm	Permutation
d	Subsystem dimensions

Returns

Permuted system, as a dynamic matrix over the same scalar field as A

6.1.4.178 TFQ()

Inverse (adjoint) qudit quantum Fourier transform.

Parameters

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Inverse (adjoint) qudit quantum Fourier transform applied on A

6.1.4.179 trace()

Trace.

Parameters

```
A Eigen expression
```

Returns

Trace of A, as a scalar over the same scalar field as A

6.1.4.180 transpose()

Transpose.

Parameters

```
A Eigen expression
```

Returns

Transpose of A, as a dynamic matrix over the same scalar field as A

```
6.1.4.181 tsallis() [1/2] template<typename Derived > double qpp::tsallis ( const Eigen::MatrixBase< Derived > & A, double q)
```

Tsallis- q entropy of the density matrix A, for $q \ge 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the von-Neumann entropy, with the logarithm in base e

Parameters

Α	Eigen expression
q	Non-negative real number

Returns

Tsallis- q entropy

```
6.1.4.182 tsallis() [2/2] double qpp::tsallis ( const std::vector< double > & prob, double q ) [inline]
```

Tsallis- q entropy of the probability distribution prob, for $q \ge 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the Shannon entropy, with the logarithm in base e

Parameters

prob	Real probability vector
q	Non-negative real number

Returns

Tsallis- q entropy

6.1.4.183 uniform()

```
std::vector<double> qpp::uniform (
    idx N ) [inline]
```

Uniform probability distribution vector.

Parameters

N Size of the alphabet

Returns

Real vector consisting of a uniform distribution of size N

6.1.4.184 var()

Variance.

Parameters

prob	Real probability vector representing the probability distribution of X
Χ	Real random variable values represented by an STL-like container

Returns

Variance of X

6.1.4.185 x2contfrac()

Simple continued fraction expansion.

See also

```
qpp::contfrac2x()
```

Parameters

Х	Real number
Ν	Maximum number of terms in the expansion
cut	Stop the expansion when the next term is greater than cut

Returns

Integer vector containing the simple continued fraction expansion of x. If there are M less than N terms in the expansion, a shorter vector with M components is returned.

6.1.5 Variable Documentation

6.1.5.1 chop

```
constexpr double qpp::chop = 1e-16
```

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

6.1.5.2 ee

```
constexpr double qpp::ee = 2.718281828459045235360287471352662497
```

Base of natural logarithm, e.

6.1.5.3 infty

```
constexpr double qpp::infty = std::numeric_limits<double>::max()
```

Used to denote infinity in double precision.

6.1.5.4 maxn

```
constexpr idx qpp::maxn = 64
```

Maximum number of allowed qubits/qudits (subsystems)

Used internally to allocate arrays on the stack (for performance reasons):

6.1.5.5 pi

```
constexpr double qpp::pi = 3.141592653589793238462643383279502884 \pi
```

6.2 qpp::exception Namespace Reference

Quantum++ exception hierarchy namespace.

Classes

class CustomException

Custom exception.

· class DimsInvalid

Invalid dimension(s) exception.

· class DimsMismatchCvector

Dimension(s) mismatch column vector size exception.

· class DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

· class DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

· class DimsMismatchVector

Dimension(s) mismatch vector size exception.

· class DimsNotEqual

Dimensions not equal exception.

class Duplicates

System (e.g. std::vector) has duplicates exception.

class Exception

Base class for generating Quantum++ custom exceptions.

· class InvalidIterator

Invalid iterator.

class MatrixMismatchSubsys

Matrix mismatch subsystems exception.

class MatrixNotCvector

Matrix is not a column vector exception.

· class MatrixNotRvector

Matrix is not a row vector exception.

class MatrixNotSquare

Matrix is not square exception.

class MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

class MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

class MatrixNotSquareNorVector

Matrix is not square nor vector exception.

class MatrixNotVector

Matrix is not a vector exception.

class NoCodeword

Codeword does not exist exception.

· class NotBipartite

Not bi-partite exception.

class NotImplemented

Code not yet implemented.

class NotQubitCvector

Column vector is not 2 x 1 exception.

class NotQubitMatrix

Matrix is not 2 x 2 exception.

class NotQubitRvector

Row vector is not 1 x 2 exception.

class NotQubitSubsys

Subsystems are not qubits exception.

· class NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

class OutOfRange

Argument out of range exception.

class PermInvalid

Invalid permutation exception.

• class PermMismatchDims

Permutation mismatch dimensions exception.

· class QuditAlreadyMeasured

Qudit was already measured exception.

· class SizeMismatch

Size mismatch exception.

· class SubsysMismatchDims

Subsystems mismatch dimensions exception.

class TypeMismatch

Type mismatch exception.

class UndefinedType

Not defined for this type exception.

· class Unknown

Unknown exception.

· class ZeroSize

Object has zero size exception.

6.2.1 Detailed Description

Quantum++ exception hierarchy namespace.

6.3 qpp::experimental Namespace Reference

Experimental/test functions/classes, do not use or modify.

6.3.1 Detailed Description

Experimental/test functions/classes, do not use or modify.

6.4 qpp::internal Namespace Reference

Internal utility functions, do not use them directly or modify them.

Classes

- struct Display_Impl_
- class EqualEigen

Functor for comparing Eigen expressions for equality.

class EqualSameSizeStringDits

Functor for comparing strings of numbers of equal sizes in lexicographical order. Establishes a strict weak ordering relation.

· class HashEigen

Functor for hashing Eigen expressions.

- class IOManipEigen
- class IOManipPointer
- · class IOManipRange
- class Singleton

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Functions

template < class T > void hash_combine (std::size_t &seed, const T &v)

Hash combine.

- void n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- $\bullet \ \ {\sf template}{<} {\sf typename \ Derived} >$

bool check_square_mat (const Eigen::MatrixBase< Derived > &A)

• template<typename Derived >

bool check_vector (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

bool bool check_rvector (const Eigen::MatrixBase Derived > &A)

 $\bullet \ \ \text{template}{<} \text{typename Derived} >$

bool check_cvector (const Eigen::MatrixBase Derived > &A)

• template<typename T >

bool check_nonzero_size (const T &x) noexcept

• template<typename T1 , typename T2 >

bool check_matching_sizes (const T1 &lhs, const T2 &rhs) noexcept

- bool check_dims (const std::vector< idx > &dims)
- template<typename Derived >

 $bool\ check_dims_match_mat\ (const\ std::vector < idx > \&dims,\ const\ Eigen::MatrixBase < Derived > \&A)$

• template<typename Derived >

bool check_dims_match_cvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

• template<typename Derived >

bool check_dims_match_rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- bool check eq dims (const std::vector< idx > &dims, idx dim) noexcept
- bool check no duplicates (std::vector < idx > v)
- bool check_subsys_match_dims (const std::vector < idx > &subsys, const std::vector < idx > &dims)
- template<typename Derived >

bool check_qubit_matrix (const Eigen::MatrixBase< Derived > &A) noexcept

• template<typename Derived >

 $bool\ check_qubit_cvector\ (const\ Eigen::MatrixBase < Derived > \&A)\ no except$

• template<typename Derived >

bool check qubit rvector (const Eigen::MatrixBase< Derived > &A) noexcept

• template<typename Derived >

bool check_qubit_vector (const Eigen::MatrixBase< Derived > &A) noexcept

- bool check_perm (const std::vector< idx > &perm)
- template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > kron2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::
 MatrixBase< Derived2 > &B)
- template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > dirsum2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen
 ::MatrixBase< Derived2 > &B)
- template<typename T >
 void variadic_vector_emplace (std::vector< T > &)
- template<typename T, typename First, typename... Args>
 void variadic_vector_emplace (std::vector< T > &v, First &&first, Args &&... args)
- idx get_num_subsys (idx D, idx d)
- idx get_dim_subsys (idx sz, idx N)
- template<typename T, typename std::enable_if< std::numeric_limits< T >::is_iec559||is_complex< T >::value >::type * = nullptr>
 T abs_chop (const T &x, double chop=qpp::chop)
- template<typename T, typename std::enable_if<!(std::numeric_limits< T >::is_iec559||is_complex< T >::value)>::type * = nullptr> T abs_chop (const T &x, double QPP_UNUSED_chop=qpp::chop)

6.4.1 Detailed Description

Internal utility functions, do not use them directly or modify them.

6.4.2 Function Documentation

```
6.4.2.1 abs_chop() [1/2]
```

```
template<typename T , typename std::enable_if< std::numeric_limits< T >::is_iec559||is_\leftarrow complex< T >::value >::type * = nullptr> T qpp::internal::abs_chop ( const T & x, double chop = qpp::chop )
```

6.4.2.2 abs_chop() [2/2]

```
6.4.2.3 check_cvector()
```

```
template<typename Derived >
bool qpp::internal::check_cvector (
             const Eigen::MatrixBase< Derived > & A )
6.4.2.4 check_dims()
bool qpp::internal::check_dims (
             const std::vector< idx > & dims ) [inline]
6.4.2.5 check_dims_match_cvect()
{\tt template}{<}{\tt typename \ Derived} \,>\,
bool qpp::internal::check\_dims\_match\_cvect (
             const std::vector< idx > & dims,
             const Eigen::MatrixBase< Derived > & A )
6.4.2.6 check_dims_match_mat()
template<typename Derived >
bool qpp::internal::check_dims_match_mat (
             const std::vector< idx > & dims,
             const Eigen::MatrixBase< Derived > & A )
6.4.2.7 check_dims_match_rvect()
template < typename Derived >
bool qpp::internal::check_dims_match_rvect (
             const std::vector< idx > & dims,
             const Eigen::MatrixBase< Derived > & A )
6.4.2.8 check_eq_dims()
bool qpp::internal::check_eq_dims (
             const std::vector< idx > & dims,
             idx dim ) [inline], [noexcept]
```

6.4.2.9 check_matching_sizes()

```
template<typename T1 , typename T2 >
bool qpp::internal::check_matching_sizes (
            const T1 & lhs,
             const T2 & rhs ) [noexcept]
6.4.2.10 check_no_duplicates()
bool qpp::internal::check_no_duplicates (
            std::vector < idx > v) [inline]
6.4.2.11 check_nonzero_size()
template<typename T >
bool qpp::internal::check_nonzero_size (
            const T & x ) [noexcept]
6.4.2.12 check_perm()
bool qpp::internal::check_perm (
            const std::vector< idx > & perm ) [inline]
6.4.2.13 check_qubit_cvector()
template<typename Derived >
bool qpp::internal::check_qubit_cvector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.14 check_qubit_matrix()
template<typename Derived >
bool qpp::internal::check_qubit_matrix (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
```

```
6.4.2.15 check_qubit_rvector()
```

```
template<typename Derived >
bool qpp::internal::check_qubit_rvector (
             const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.16 check_qubit_vector()
template<typename Derived >
bool qpp::internal::check_qubit_vector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.17 check_rvector()
template<typename Derived >
bool qpp::internal::check_rvector (
             const Eigen::MatrixBase< Derived > & A )
6.4.2.18 check_square_mat()
template < typename Derived >
bool qpp::internal::check_square_mat (
             const Eigen::MatrixBase< Derived > & A )
6.4.2.19 check_subsys_match_dims()
bool qpp::internal::check_subsys_match_dims (
            const std::vector< idx > & subsys,
             const std::vector< idx > & dims ) [inline]
6.4.2.20 check_vector()
template < typename Derived >
bool qpp::internal::check_vector (
            const Eigen::MatrixBase< Derived > & A )
```

6.4.2.21 dirsum2()

6.4.2.22 get_dim_subsys()

6.4.2.23 get_num_subsys()

6.4.2.24 hash_combine()

Hash combine.

Template Parameters

|--|

Parameters

seed	Initial seed, will be updated by the function
V	Value with which the hash is combined

6.4.2.25 kron2()

```
template<typename Derived1 , typename Derived2 >
dyn_mat<typename Derived1::Scalar> qpp::internal::kron2 (
```

```
const Eigen::MatrixBase< Derived1 > & A,
const Eigen::MatrixBase< Derived2 > & B )
```

6.4.2.26 multiidx2n()

6.4.2.27 n2multiidx()

6.4.2.28 variadic_vector_emplace() [1/2]

```
template<typename T > void qpp::internal::variadic_vector_emplace ( std::vector < T \ > \& \ )
```

6.4.2.29 variadic_vector_emplace() [2/2]

6.5 qpp::literals Namespace Reference

Functions

```
• constexpr cplx operator""_i (unsigned long long int x) noexcept
      User-defined literal for complex i = \sqrt{-1} (integer overload)

    constexpr cplx operator""_i (long double x) noexcept

      User-defined literal for complex i = \sqrt{-1} (real overload)
• constexpr std::complex< float > operator""_if (unsigned long long int x) noexcept
      User-defined literal for complex i = \sqrt{-1} (integer overload)
• constexpr std::complex< float > operator""_if (long double x) noexcept
      User-defined literal for complex i = \sqrt{-1} (real overload)
• template<char... Bits>
  ket operator""_ket ()
      Multi-partite qubit ket user-defined literal.
• template<char... Bits>
  bra operator""_bra ()
      Multi-partite qubit bra user-defined literal.
• template<char... Bits>
  cmat operator""_prj ()
      Multi-partite qubit projector user-defined literal.
```

6.5.1 Function Documentation

```
6.5.1.1 operator"""_bra()

template<char... Bits>
bra qpp::literals::operator""_bra ( )
```

Multi-partite qubit bra user-defined literal.

See also

```
qpp::mket() and qpp::adjoint()
```

Constructs the multi-partite qubit bra $\langle Bits |$

Template Parameters

Bits String of binary numbers representing the qubit bra

Returns

Multi-partite qubit bra, as a complex dynamic row vector

```
6.5.1.2 operator"""_i() [1/2]
constexpr cplx qpp::literals::operator""_i (
              unsigned long long int x ) [inline], [noexcept]
User-defined literal for complex i = \sqrt{-1} (integer overload)
Example:
cplx z = 4_i; // type of z is std::complex<double>
6.5.1.3 operator"""_i() [2/2]
constexpr cplx qpp::literals::operator""_i (
              long double x ) [inline], [noexcept]
User-defined literal for complex i = \sqrt{-1} (real overload)
Example:
cplx z = 4.5_i; // type of z is std::complex<double>
6.5.1.4 operator"""_if() [1/2]
constexpr std::complex<float> qpp::literals::operator""_if (
              unsigned long long int x ) [inline], [noexcept]
User-defined literal for complex i = \sqrt{-1} (integer overload)
Example:
auto \dot{z} = 4_if; // type of z is std::complex<double>
6.5.1.5 operator"""_if() [2/2]
constexpr std::complex<float> qpp::literals::operator""_if (
              long double x ) [inline], [noexcept]
User-defined literal for complex i = \sqrt{-1} (real overload)
Example:
auto z = 4.5_if; // type of z is std::complex<float>
6.5.1.6 operator"""_ket()
template<char... Bits>
ket qpp::literals::operator""_ket ( )
Multi-partite qubit ket user-defined literal.
See also
     qpp::mket()
```

Constructs the multi-partite qubit ket $|Bits\rangle$

Template Parameters

Bits	String of binary numbers representing the qubit ket	
------	---	--

Returns

Multi-partite qubit ket, as a complex dynamic column vector

6.5.1.7 operator"""_prj()

```
template<char... Bits>
cmat qpp::literals::operator""_prj ( )
```

Multi-partite qubit projector user-defined literal.

See also

qpp::mprj()

Constructs the multi-partite qubit projector $|Bits\rangle\langle Bits|$ (in the computational basis)

Template Parameters

Bits String of binary numbers representing the qubit state to project on

Returns

Multi-partite qubit projector, as a complex dynamic matrix

Chapter 7

Class Documentation

7.1 qpp::Bit_circuit Class Reference


Classical reversible circuit simulator.

#include <classes/reversible.h>

Inheritance diagram for qpp::Bit_circuit:



Collaboration diagram for qpp::Bit_circuit:



Public Member Functions

• Bit_circuit (idx n)

Constructs a bit circuit instance.

• Bit_circuit (const Dynamic_bitset &dynamic_bitset)

Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.

Bit_circuit & X (idx i)

Bit flip.

• virtual \sim Bit_circuit ()=default

Default virtual destructor.

• Bit_circuit & NOT (idx i)

Bit flip.

• Bit_circuit & CNOT (idx ctrl, idx target)

Controlled-NOT.

• Bit_circuit & TOF (idx i, idx j, idx k)

Toffoli gate.

• Bit_circuit & SWAP (idx i, idx j)

Swap bits.

• Bit_circuit & FRED (idx i, idx j, idx k)

Fredkin gate (Controlled-SWAP)

Bit_circuit & reset () noexcept

Reset the circuit all zero, clear all gates.

- idx get_gate_count (const std::string &name={}) const Bit circuit gate count.
- idx get_gate_depth (const std::string &name={}) const Bit circuit gate depth.

Private Attributes

- std::unordered_map< std::string, idx > depth_ {}
 gate depths
- Dynamic_bitset bNOT_
- Dynamic_bitset bCNOT_
- Dynamic_bitset bSWAP_
- Dynamic_bitset bTOF_
- Dynamic_bitset bFRED_
- Dynamic_bitset btotal_

used for depth calculations

Additional Inherited Members

7.1.1 Detailed Description

Classical reversible circuit simulator.

7.1.2 Constructor & Destructor Documentation

```
7.1.2.1 Bit_circuit() [1/2]

qpp::Bit_circuit::Bit_circuit (
        idx n ) [inline], [explicit]
```

Constructs a bit circuit instance.

Parameters

n Number of classical bits

Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.

Parameters

```
dynamic_bitset Dynamic bitset
```

```
7.1.2.3 ∼Bit_circuit()
```

```
virtual qpp::Bit_circuit::~Bit_circuit ( ) [virtual], [default]
```

Default virtual destructor.

7.1.3 Member Function Documentation

7.1.3.1 CNOT()

Controlled-NOT.

Parameters

ctrl	Control bit index
target	Target bit index

Returns

Reference to the current instance

7.1.3.2 FRED()

```
Bit_circuit& qpp::Bit_circuit::FRED (
    idx i,
    idx j,
    idx k) [inline]
```

Fredkin gate (Controlled-SWAP)

Parameters

i Control bit index	
j Target first bit index	
k	Target second bit index

Returns

Reference to the current instance

7.1.3.3 get_gate_count()

Bit circuit gate count.

Note

If name is empty (default), returns the total gate count of the circuit

Parameters

Returns

Gate count

7.1.3.4 get_gate_depth()

Bit circuit gate depth.

Note

If name is empty (default), returns the total gate depth of the circuit

Parameters

name	Gate name (option	nal). Possible names are N	NOT (X), CNOT, SWAP, TOF, FRED.

```
Returns
```

Gate depth

```
7.1.3.5 NOT()
```

```
Bit_circuit& qpp::Bit_circuit::NOT (
        idx i ) [inline]
```

Bit flip.

See also

```
qpp::Bit_circuit::X()
```

Parameters

```
i Bit position in the circuit
```

Returns

Reference to the current instance

```
7.1.3.6 reset()
```

```
Bit_circuit& qpp::Bit_circuit::reset ( ) [inline], [noexcept]
```

Reset the circuit all zero, clear all gates.

Returns

Reference to the current instance

7.1.3.7 SWAP()

```
Bit_circuit& qpp::Bit_circuit::SWAP (
         idx i,
         idx j) [inline]
```

Swap bits.

Parameters

i	Bit index
j	Bit index

Returns

Reference to the current instance

7.1.3.8 TOF()

```
Bit_circuit& qpp::Bit_circuit::TOF (
    idx i,
    idx j,
    idx k) [inline]
```

Toffoli gate.

Parameters

i	Control first bit index
j	Control second bit index
k	Target bit index

Returns

Reference to the current instance

7.1.3.9 X()

```
Bit_circuit& qpp::Bit_circuit::X (
        idx i) [inline]
```

Bit flip.

See also

```
qpp::Bit_circuit::NOT()
```

Parameters

i Bit position in the circuit

Returns

Reference to the current instance

7.1.4 Member Data Documentation

```
7.1.4.1 bCNOT_
Dynamic_bitset qpp::Bit_circuit::bCNOT_ [private]
7.1.4.2 bFRED_
Dynamic_bitset qpp::Bit_circuit::bFRED_ [private]
7.1.4.3 bNOT_
Dynamic_bitset qpp::Bit_circuit::bNOT_ [private]
7.1.4.4 bSWAP_
Dynamic_bitset qpp::Bit_circuit::bSWAP_ [private]
7.1.4.5 bTOF_
Dynamic_bitset qpp::Bit_circuit::bTOF_ [private]
7.1.4.6 btotal_
Dynamic_bitset qpp::Bit_circuit::btotal_ [private]
used for depth calculations
```

```
7.1.4.7 count_
```

```
std::unordered_map<std::string, idx> qpp::Bit_circuit::count_ {} [private]
gate counts
```

7.1.4.8 depth_

```
std::unordered_map<std::string, idx> qpp::Bit_circuit::depth_ {} [private]
gate depths
```

The documentation for this class was generated from the following file:


· classes/reversible.h

7.2 qpp::Codes Class Reference


const Singleton class that defines quantum error correcting codes

```
#include <classes/codes.h>
```

Inheritance diagram for qpp::Codes:



Collaboration diagram for qpp::Codes:



Public Types

enum Type { Type::FIVE_QUBIT, Type::SEVEN_QUBIT_STEANE, Type::NINE_QUBIT_SHOR }
 Code types, add more codes here if needed.

Public Member Functions

ket codeword (Type type, idx i) const
 Returns the codeword of the specified code type.

Private Member Functions

• Codes ()

Default constructor.

∼Codes ()=default

Default destructor.

Friends

class internal::Singleton < const Codes >

Additional Inherited Members

7.2.1 Detailed Description

const Singleton class that defines quantum error correcting codes

7.2.2 Member Enumeration Documentation

7.2.2.1 Type

```
enum qpp::Codes::Type [strong]
```

Code types, add more codes here if needed.

See also

qpp::Codes::codeword()

Enumerator

FIVE_QUBIT	[[5,1,3]] qubit code
SEVEN_QUBIT_STEANE	[[7,1,3]] Steane qubit code
NINE_QUBIT_SHOR	[[9,1,3]] Shor qubit code

7.2.3 Constructor & Destructor Documentation

7.2.3.1 Codes()

```
qpp::Codes::Codes ( ) [inline], [private]
```

Default constructor.

7.2.3.2 ∼Codes()

```
qpp::Codes::~Codes ( ) [private], [default]
```

Default destructor.

7.2.4 Member Function Documentation

7.2.4.1 codeword()

Returns the codeword of the specified code type.

See also

```
qpp::Codes::Type
```

Parameters

type	Code type
i	Codeword index

Returns

i-th codeword of the code type

7.2.5 Friends And Related Function Documentation

7.2.5.1 internal::Singleton < const Codes >

```
friend class internal::Singleton< const Codes > [friend]
```

The documentation for this class was generated from the following file:


· classes/codes.h

7.3 qpp::exception::CustomException Class Reference


Custom exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::CustomException:



Collaboration diagram for qpp::exception::CustomException:



Public Member Functions

• CustomException (const std::string &where, const std::string &what)

Private Member Functions

• std::string description () const override Exception description.

Private Attributes

std::string what_{{}}

7.3.1 Detailed Description

Custom exception.

Custom exception, the user must provide a custom message

7.3.2 Constructor & Destructor Documentation

7.3.2.1 CustomException()

7.3.3 Member Function Documentation

7.3.3.1 description()

```
std::string qpp::exception::CustomException::description ( ) const [inline], [override],
[private], [virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.3.4 Member Data Documentation

7.3.4.1 what_

```
std::string qpp::exception::CustomException::what_ {} [private]
```

The documentation for this class was generated from the following file:


· classes/exception.h

7.4 qpp::exception::DimsInvalid Class Reference

Invalid dimension(s) exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsInvalid:



Collaboration diagram for qpp::exception::DimsInvalid:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.4.1 Detailed Description

Invalid dimension(s) exception.

std::vector<idx> of dimensions has zero size or contains zeros

7.4.2 Member Function Documentation

7.4.2.1 description()

std::string qpp::exception::DimsInvalid::description () const [inline], [override], [virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.4.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.5 qpp::exception::DimsMismatchCvector Class Reference


Dimension(s) mismatch column vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchCvector:



Collaboration diagram for qpp::exception::DimsMismatchCvector:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.5.1 Detailed Description

Dimension(s) mismatch column vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a column vector)

7.5.2 Member Function Documentation

7.5.2.1 description()

std::string qpp::exception::DimsMismatchCvector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.5.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.6 qpp::exception::DimsMismatchMatrix Class Reference


Dimension(s) mismatch matrix size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchMatrix:



Collaboration diagram for qpp::exception::DimsMismatchMatrix:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.6.1 Detailed Description

Dimension(s) mismatch matrix size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of rows of the Eigen::Matrix (assumed to be a square matrix)

7.6.2 Member Function Documentation

7.6.2.1 description()

```
std::string qpp::exception::DimsMismatchMatrix::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.6.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.7 qpp::exception::DimsMismatchRvector Class Reference


Dimension(s) mismatch row vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchRvector:



Collaboration diagram for qpp::exception::DimsMismatchRvector:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.7.1 Detailed Description

Dimension(s) mismatch row vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row vector)

7.7.2 Member Function Documentation

7.7.2.1 description()

std::string qpp::exception::DimsMismatchRvector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.7.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


classes/exception.h

7.8 qpp::exception::DimsMismatchVector Class Reference


Dimension(s) mismatch vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchVector:



Collaboration diagram for qpp::exception::DimsMismatchVector:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.8.1 Detailed Description

Dimension(s) mismatch vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row/column vector)

7.8.2 Member Function Documentation

7.8.2.1 description()

std::string qpp::exception::DimsMismatchVector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.8.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


classes/exception.h

7.9 qpp::exception::DimsNotEqual Class Reference


Dimensions not equal exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsNotEqual:



Collaboration diagram for qpp::exception::DimsNotEqual:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.9.1 Detailed Description

Dimensions not equal exception.

Local/global dimensions are not equal

7.9.2 Member Function Documentation

7.9.2.1 description()

std::string qpp::exception::DimsNotEqual::description () const [inline], [override], [virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.9.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:

· classes/exception.h

7.10 qpp::internal::Display_Impl_ Struct Reference

```
#include <internal/util.h>
```

Inheritance diagram for qpp::internal::Display_Impl_:



Public Member Functions

template<typename T >
 std::ostream & display_impl_ (const T &A, std::ostream &os, double chop=qpp::chop) const

7.10.1 Member Function Documentation

7.10.1.1 display_impl_()

The documentation for this struct was generated from the following file:


• internal/util.h

7.11 qpp::exception::Duplicates Class Reference


System (e.g. std::vector) has duplicates exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Duplicates:



Collaboration diagram for qpp::exception::Duplicates:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.11.1 Detailed Description

System (e.g. std::vector) has duplicates exception.

7.11.2 Member Function Documentation

7.11.2.1 description()

```
std::string qpp::exception::Duplicates::description ( ) const [inline], [override], [virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.11.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.12 qpp::Dynamic_bitset Class Reference


Dynamic bitset class, allows the specification of the number of bits at runtime.

#include <classes/reversible.h>

Inheritance diagram for qpp::Dynamic_bitset:



Collaboration diagram for qpp::Dynamic_bitset:



Public Types

- using value_type = unsigned int type of the storage elements
- using storage_type = std::vector< value_type > type of the storage

Public Member Functions

• Dynamic_bitset (idx n)

Constructor, initializes all bits to false (zero)

virtual ~Dynamic_bitset ()=default

Default virtual destructor.

const storage_type & data () const

Raw storage space of the bitset.

idx size () const noexcept

Number of bits stored in the bitset.

• idx storage_size () const noexcept

Size of the underlying storage space (in units of value_type, unsigned int by default)

· idx count () const noexcept

Number of bits set to one in the bitset (Hamming weight)

· bool get (idx pos) const noexcept

The value of the bit at position pos.

• bool none () const noexcept

Checks whether none of the bits are set.

• bool all () const noexcept

Checks whether all bits are set.

· bool any () const noexcept

Checks whether any bit is set.

Dynamic_bitset & set (idx pos, bool value=true)

Sets the bit at position pos.

• Dynamic_bitset & set () noexcept

Set all bits to true.

Dynamic_bitset & rand (idx pos, double p=0.5)

Sets the bit at position pos according to a Bernoulli(p) distribution.

Dynamic_bitset & rand (double p=0.5)

Sets all bits according to a Bernoulli(p) distribution.

• Dynamic_bitset & reset (idx pos)

Sets the bit at position pos to false.

• Dynamic_bitset & reset () noexcept

Sets all bits to false.

• Dynamic_bitset & flip (idx pos)

Flips the bit at position pos.

• Dynamic_bitset & flip () noexcept

Flips all bits.

bool operator== (const Dynamic_bitset &rhs) const noexcept

Equality operator.

bool operator!= (const Dynamic_bitset &rhs) const noexcept

Inequality operator.

idx operator- (const Dynamic_bitset &rhs) const noexcept

Number of places the two bitsets differ (Hamming distance)

template < class CharT = char, class Traits = std::char_traits < CharT>, class Allocator = std::allocator < CharT>> std::basic_string < CharT, Traits, Allocator > to_string (CharT zero=CharT('0'), CharT one=CharT('1')) const String representation.

Protected Member Functions

• idx index_ (idx pos) const

Index of the pos bit in the storage space.

idx offset_ (idx pos) const

Offset of the pos bit in the storage space relative to its index.

Protected Attributes

```
    idx storage_size_
        storage size
    idx n_
        number of bits
    std::vector < value_type > v_
        storage space
```

Private Member Functions

7.12.1 Detailed Description

Dynamic bitset class, allows the specification of the number of bits at runtime.

Note

The interface mimics std::bitset<>

7.12.2 Member Typedef Documentation

```
7.12.2.1 storage_type
using qpp::Dynamic_bitset::storage_type = std::vector<value_type>
type of the storage

7.12.2.2 value_type
using qpp::Dynamic_bitset::value_type = unsigned int
type of the storage elements
```

7.12.3 Constructor & Destructor Documentation

```
7.12.3.1 Dynamic_bitset()
```

```
qpp::Dynamic_bitset ::Dynamic_bitset (
          idx n ) [inline], [explicit]
```

Constructor, initializes all bits to false (zero)

```
Parameters
```

n Number of bits in the bitset

```
7.12.3.2 ~Dynamic_bitset()
```

```
virtual qpp::Dynamic_bitset::~Dynamic_bitset ( ) [virtual], [default]
```

Default virtual destructor.

7.12.4 Member Function Documentation

```
7.12.4.1 all()
```

```
bool qpp::Dynamic_bitset::all ( ) const [inline], [noexcept]
```

Checks whether all bits are set.

Returns

True if all of the bits are set

7.12.4.2 any()

```
bool qpp::Dynamic_bitset::any ( ) const [inline], [noexcept]
```

Checks whether any bit is set.

Returns

True if any of the bits is set

7.12.4.3 count()

```
idx qpp::Dynamic_bitset::count ( ) const [inline], [noexcept]
```

Number of bits set to one in the bitset (Hamming weight)

Returns

Hamming weight

7.12.4.4 data()

```
const storage_type& qpp::Dynamic_bitset::data ( ) const [inline]
```

Raw storage space of the bitset.

Returns

Const reference to the underlying storage space

7.12.4.5 display()

qpp::IDisplay::display() override, displays the bitset bit by bit

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.12.4.6 flip() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip (
        idx pos ) [inline]
```

Flips the bit at position pos.

Parameters

pos Position in the bitset

Returns

Reference to the current instance

```
7.12.4.7 flip() [2/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip ( ) [inline], [noexcept]
```

Flips all bits.

Returns

Reference to the current instance

7.12.4.8 get()

```
bool qpp::Dynamic_bitset::get (
          idx pos ) const [inline], [noexcept]
```

The value of the bit at position pos.

Parameters

pos Position in the bitset

Returns

Value of the bit at position pos

7.12.4.9 index_()

Index of the pos bit in the storage space.

Parameters

```
pos Bit location
```

Returns

Index of the pos bit in the storage space

7.12.4.10 none()

```
bool qpp::Dynamic_bitset::none ( ) const [inline], [noexcept]
```

Checks whether none of the bits are set.

Returns

True if none of the bits are set

7.12.4.11 offset_()

Offset of the pos bit in the storage space relative to its index.

Parameters

```
pos Bit location
```

Returns

Offset of the pos bit in the storage space relative to its index

7.12.4.12 operator"!=()

Inequality operator.

Parameters

```
rhs Dynamic_bitset against which the inequality is being tested
```

Returns

True if the bitsets are not equal (bit by bit), false otherwise

7.12.4.13 operator-()

Number of places the two bitsets differ (Hamming distance)

Parameters

rhs Dynamic_bitset against which the Hamming distance is computed

Returns

Hamming distance

7.12.4.14 operator==()

Equality operator.

Parameters

```
rhs Dynamic_bitset against which the equality is being tested
```

Returns

True if the bitsets are equal (bit by bit), false otherwise

7.12.4.15 rand() [1/2]

```
Dynamic_bitset& qpp::Dynamic_bitset::rand (
    idx pos,
    double p = 0.5 ) [inline]
```

Sets the bit at position *pos* according to a Bernoulli(p) distribution.

Parameters

pos	Position in the bitset
р	Probability

Returns

Reference to the current instance

Sets all bits according to a Bernoulli(p) distribution.

Parameters

```
p Probability
```

Returns

Reference to the current instance

Sets the bit at position pos to false.

Parameters

```
pos Position in the bitset
```

Returns

Reference to the current instance

```
7.12.4.18 reset() [2/2]
Dynamic_bitset& qpp::Dynamic_bitset::reset ( ) [inline], [noexcept]
Sets all bits to false.
```

Returns

Reference to the current instance

```
7.12.4.19 set() [1/2]
```

Sets the bit at position pos.

Parameters

pos	Position in the bitset
value	Bit value

Returns

Reference to the current instance

```
7.12.4.20 set() [2/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::set () [inline], [noexcept]
```

Set all bits to true.

Returns

Reference to the current instance

7.12.4.21 size()

```
idx qpp::Dynamic_bitset::size ( ) const [inline], [noexcept]
```

Number of bits stored in the bitset.

Returns

Number of bits stored in the bitset

7.12.4.22 storage_size()

```
idx qpp::Dynamic_bitset::storage_size ( ) const [inline], [noexcept]
```

Size of the underlying storage space (in units of value_type, unsigned int by default)

Returns

Size of the underlying storage space

7.12.4.23 to_string()

String representation.

Template Parameters

CharT	String character type
Traits	String traits
Allocator	String Allocator

Parameters

zero	Character representing the zero
one	Character representing the one

Returns

Bitset as a string

7.12.5 Member Data Documentation

```
7.12.5.1 n_
idx qpp::Dynamic_bitset::n_ [protected]
```

7.12.5.2 storage_size_

number of bits

```
idx qpp::Dynamic_bitset::storage_size_ [protected]
```

storage size

```
7.12.5.3 v_
std::vector<value_type> qpp::Dynamic_bitset::v_ [protected]
storage space
```

The documentation for this class was generated from the following file:

classes/reversible.h

7.13 qpp::internal::EqualEigen Class Reference

Functor for comparing Eigen expressions for equality.

```
#include <functions.h>
```

Public Member Functions

template<typename Derived >
 bool operator() (const Eigen::MatrixBase< Derived > &A, const Eigen::MatrixBase< Derived > &B) const

7.13.1 Detailed Description

Functor for comparing Eigen expressions for equality.

Note

Works without assertion fails even if the dimensions of the arguments are different (in which case it simply returns false)

7.13.2 Member Function Documentation

7.13.2.1 operator()()

The documentation for this class was generated from the following file:

· functions.h

7.14 qpp::internal::EqualSameSizeStringDits Class Reference

Functor for comparing strings of numbers of equal sizes in lexicographical order. Establishes a strict weak ordering relation.

```
#include <functions.h>
```

Public Member Functions

• bool operator() (const std::string &s1, const std::string &s2) const

7.14.1 Detailed Description

Functor for comparing strings of numbers of equal sizes in lexicographical order. Establishes a strict weak ordering relation.

Note

Used as a hash table comparator in qpp::QEngine

7.14.2 Member Function Documentation

7.14.2.1 operator()()

The documentation for this class was generated from the following file:


· functions.h

7.15 qpp::exception::Exception Class Reference


Base class for generating Quantum++ custom exceptions.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Exception:



Collaboration diagram for qpp::exception::Exception:



Public Member Functions

- Exception (const std::string &where)
 - Constructs an exception.
- const char * what () const noexcept override
 - Overrides std::exception::what()
- virtual std::string description () const =0

Exception description.

Private Attributes

- std::string where
- std::string msg

7.15.1 Detailed Description

Base class for generating Quantum++ custom exceptions.

Derive from this class if more exceptions are needed, making sure to override qpp::exception::Exception::Exception::description() in the derived class and to inherit the constructor qpp::exception::Exception::Exception(). Preferably keep your newly defined exception classes in the namespace qpp::exception.

Example:

```
namespace qpp
{
namespace exception
{
    class ZeroSize : public Exception
    {
        public:
            std::string description() const override
            {
                  return "Object has zero size";
            }
            // inherit the base class' qpp::exception::Exception constructor using Exception::Exception;
        };
} // namespace exception
} // namespace qpp
```

7.15.2 Constructor & Destructor Documentation

7.15.2.1 Exception()

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.15.3 Member Function Documentation

7.15.3.1 description()

```
std::string qpp::exception::Exception::description ( ) const [inline], [pure virtual]
```

Exception description.

Returns

Exception description

Implemented in qpp::exception::InvalidIterator, qpp::exception::NotImplemented, qpp::exception::CustomException, qpp::exception::Duplicates, qpp::exception::QuditAlreadyMeasured, qpp::exception::UndefinedType, qpp::exception::SizeMismatch, qpp::exception::TypeMismatch, qpp::exception::OutOfRange, qpp::exception::NotOdeword, qpp::exception::NotBipartite, qpp::exception::NotQubitSubsys, qpp::exception::NotQubitVector, qpp::exception::NotQubitRvector, qpp::exception::NotQubitCvector qpp::exception::NotQubitMatrix, qpp::exception::PermMismatchDims, qpp::exception::PermInvalid, qpp::exception::SubsysMismatchEqpp::exception::DimsMismatchVector, qpp::exception::DimsMismatchCvector, qpp::exception::DimsMismatchMatrix, qpp::exception::DimsNotEqual, qpp::exception::DimsInvalid, qpp::exception::MatrixMismatchSu qpp::exception::MatrixNotSquareNorVector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::Unknown.

```
7.15.3.2 what()
```

```
const char* qpp::exception::Exception::what ( ) const [inline], [override], [noexcept]
```

Overrides std::exception::what()

Returns

Exception description

7.15.4 Member Data Documentation

7.15.4.1 msg_

std::string qpp::exception::Exception::msg_ [mutable], [private]

7.15.4.2 where_

std::string qpp::exception::Exception::where_ [private]

The documentation for this class was generated from the following file:


· classes/exception.h

7.16 qpp::Gates Class Reference


const Singleton class that implements most commonly used gates

#include <classes/gates.h>

Inheritance diagram for qpp::Gates:



Collaboration diagram for qpp::Gates:



Public Member Functions

cmat Rn (double theta, const std::vector< double > &n) const

Qubit rotation of theta about the 3-dimensional real (unit) vector n.

cmat RX (double theta) const

Qubit rotation of theta about the X axis.

cmat RY (double theta) const

Qubit rotation of theta about the Y axis.

cmat RZ (double theta) const

Qubit rotation of theta about the Z axis.

• cmat Zd (idx D=2) const

Generalized Z gate for qudits.

• cmat SWAPd (idx D=2) const

SWAP gate for qudits.

• cmat Fd (idx D=2) const

Quantum Fourier transform gate for qudits.

• cmat MODMUL (idx a, idx N, idx n) const

Modular multiplication gate for qubits Implements $|x\rangle \longrightarrow |ax \bmod N\rangle$.

• cmat Xd (idx D=2) const

Generalized X gate for qudits.

• template<typename Derived = Eigen::MatrixXcd>

Derived Id (idx D=2) const

Identity gate.

template<typename Derived >

dyn_mat< typename Derived::Scalar > CTRL (const Eigen::MatrixBase< Derived > &A, const std::vector<
idx > &ctrl, const std::vector< idx > &target, idx n, idx d=2) const

Generates the multi-partite multiple-controlled-A gate in matrix form.

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
std::vector< idx > &dims) const

Expands out.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
std::initializer_list< idx > &dims) const

Expands out.

template<typename Derived >

dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, idx n,
idx d=2) const

Expands out.

std::string get_name (const cmat &U) const

Get the name of the most common qubit gates.

Public Attributes

cmat Id2 {cmat::Identity(2, 2)}

Identity gate.

cmat H {cmat::Zero(2, 2)}

Hadamard gate.

cmat X {cmat::Zero(2, 2)}

Pauli Sigma-X gate.

cmat Y {cmat::Zero(2, 2)}

```
Pauli Sigma-Y gate.

    cmat Z {cmat::Zero(2, 2)}

     Pauli Sigma-Z gate.

    cmat S {cmat::Zero(2, 2)}

     S gate.

    cmat T {cmat::Zero(2, 2)}

      T gate.
cmat CNOT {cmat::ldentity(4, 4)}
     Controlled-NOT control target gate.
cmat CZ {cmat::Identity(4, 4)}
     Controlled-Phase gate.
cmat CNOTba {cmat::Zero(4, 4)}
     Controlled-NOT target->control gate.
• cmat SWAP {cmat::Identity(4, 4)}
     SWAP gate.
• cmat TOF {cmat::ldentity(8, 8)}
      Toffoli gate.
cmat FRED {cmat::Identity(8, 8)}
     Fredkin gate.
```

Private Member Functions

• Gates ()

Initializes the gates.

• ∼Gates ()=default

Default destructor.

Friends

class internal::Singleton < const Gates >

Additional Inherited Members

7.16.1 Detailed Description

const Singleton class that implements most commonly used gates

7.16.2 Constructor & Destructor Documentation

```
7.16.2.1 Gates()

qpp::Gates::Gates ( ) [inline], [private]
```

Initializes the gates.

7.16.2.2 \sim Gates()

```
qpp::Gates::~Gates ( ) [private], [default]
```

Default destructor.

7.16.3 Member Function Documentation

7.16.3.1 CTRL()

Generates the multi-partite multiple-controlled-A gate in matrix form.

See also

```
qpp::applyCTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
n	Total number of subsystems
d	Subsystem dimensions

Returns

CTRL-A gate, as a matrix over the same scalar field as A

7.16.3.2 expandout() [1/3]

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::Gates::expandout (
```

```
const Eigen::MatrixBase< Derived > & A,
idx pos,
const std::vector< idx > & dims ) const [inline]
```

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

Α	Eigen expression
pos	Position
dims	Dimensions of the multi-partite system

Returns

Tensor product $I \otimes \cdots \otimes I \otimes A \otimes I \otimes \cdots \otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.16.3.3 expandout() [2/3]

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Note

The std::initializer_list overload exists because otherwise, in the degenerate case when *dims* has only one element, the one element list is implicitly converted to the element's underlying type, i.e. qpp::idx, which has the net effect of picking the wrong (non-vector) qpp::expandout() overload

Parameters

Α	Eigen expression
pos	Position
dims	Dimensions of the multi-partite system

Returns

Tensor product $I\otimes\cdots\otimes I\otimes A\otimes I\otimes\cdots\otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.16.3.4 expandout() [3/3]

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

Α	Eigen expression
pos	Position
n	Number of subsystems
d	Subsystem dimensions

Returns

Tensor product $I \otimes \cdots \otimes I \otimes A \otimes I \otimes \cdots \otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.16.3.5 Fd()

```
cmat qpp::Gates::Fd (
    idx D = 2 ) const [inline]
```

Quantum Fourier transform gate for qudits.

Note

```
Defined as F = \sum_{j,k=0}^{D-1} \exp(2\pi \mathrm{i} jk/D) |j\rangle\langle k|
```

Parameters

D Dimension of the Hilbert space

Returns

Fourier transform gate for qudits

7.16.3.6 get_name()

Get the name of the most common qubit gates.

Note

Assumes that the gate U is represented by a square matrix. If not, returns the empty string

Parameters

U Complex matrix representing the quantum gate

Returns

Name of the gate (if any), otherwise the empty string

7.16.3.7 Id()

```
template<typename Derived = Eigen::MatrixXcd>
Derived qpp::Gates::Id (
    idx D = 2 ) const [inline]
```

Identity gate.

Note

Can change the return type from complex matrix (default) by explicitly specifying the template parameter

Parameters

D Dimension of the Hilbert space

Returns

Identity gate on a Hilbert space of dimension D

7.16.3.8 MODMUL()

```
cmat qpp::Gates::MODMUL (
          idx a,
          idx N,
          idx n ) const [inline]
```

Modular multiplication gate for qubits Implements $|x\rangle \longrightarrow |ax \mathrm{mod} N\rangle$.

Note

For the gate to be unitary, *a* and *N* should be co-prime. The function does not check co-primality in release versions!

The number of qubits required to implement the gate should satisfy $n \geq \lceil \log_2(N) \rceil$

Parameters

а	Positive integer less than N
Ν	Positive integer
n	Number of qubits required for implementing the gate

Returns

Modular multiplication gate

7.16.3.9 Rn()

Qubit rotation of *theta* about the 3-dimensional real (unit) vector *n*.

Parameters

theta	Rotation angle
n	3-dimensional real (unit) vector

Returns

Rotation gate

7.16.3.10 RX()

Qubit rotation of theta about the X axis.

Parameters

theta	Rotation angle
-------	----------------

Returns

Rotation gate

7.16.3.11 RY()

Qubit rotation of theta about the Y axis.

Parameters

theta Rotation angle

Returns

Rotation gate

7.16.3.12 RZ()

Qubit rotation of theta about the Z axis.

Parameters

theta	Rotation angle

Returns

Rotation gate

7.16.3.13 SWAPd()

```
cmat qpp::Gates::SWAPd (
    idx D = 2 ) const [inline]
```

SWAP gate for qudits.

Parameters

D Dimension of the Hilbert space

Returns

SWAP gate for qudits

7.16.3.14 Xd()

```
cmat qpp::Gates::Xd (
    idx D = 2 ) const [inline]
```

Generalized X gate for qudits.

Note

```
Defined as X=\sum_{j=0}^{D-1}|j\oplus 1\rangle\langle j|, i.e. raising operator X|j\rangle=|j\oplus 1\rangle
```

Parameters

D Dimension of the Hilbert space

Returns

Generalized X gate for qudits

7.16.3.15 Zd()

```
cmat qpp::Gates::Zd (
        idx D = 2 ) const [inline]
```

Generalized Z gate for qudits.

Note

```
Defined as Z = \sum_{j=0}^{D-1} \exp(2\pi \mathrm{i} j/D) |j\rangle\langle j|
```

Parameters

D Dimension of the Hilbert space

Returns

Generalized Z gate for qudits

7.16.4 Friends And Related Function Documentation

```
7.16.4.1 internal::Singleton < const Gates >
```

```
friend class internal::Singleton< const Gates > [friend]
```

7.16.5 Member Data Documentation

7.16.5.1 CNOT

```
cmat qpp::Gates::CNOT {cmat::Identity(4, 4)}
```

Controlled-NOT control target gate.

7.16.5.2 CNOTba

```
cmat qpp::Gates::CNOTba {cmat::Zero(4, 4)}
```

Controlled-NOT target->control gate.

7.16.5.3 CZ

```
cmat qpp::Gates::CZ {cmat::Identity(4, 4)}
```

Controlled-Phase gate.

```
7.16.5.4 FRED
cmat qpp::Gates::FRED {cmat::Identity(8, 8)}
Fredkin gate.
7.16.5.5 H
cmat qpp::Gates::H {cmat::Zero(2, 2)}
Hadamard gate.
7.16.5.6 Id2
cmat qpp::Gates::Id2 {cmat::Identity(2, 2)}
Identity gate.
7.16.5.7 S
cmat qpp::Gates::S {cmat::Zero(2, 2)}
S gate.
7.16.5.8 SWAP
cmat qpp::Gates::SWAP {cmat::Identity(4, 4)}
SWAP gate.
7.16.5.9 T
cmat qpp::Gates::T {cmat::Zero(2, 2)}
```

T gate.

```
7.16.5.10 TOF
```

```
cmat qpp::Gates::TOF {cmat::Identity(8, 8)}
```

Toffoli gate.

7.16.5.11 X

```
cmat qpp::Gates::X {cmat::Zero(2, 2)}
```

Pauli Sigma-X gate.

7.16.5.12 Y

```
cmat qpp::Gates::Y {cmat::Zero(2, 2)}
```

Pauli Sigma-Y gate.

7.16.5.13 Z

```
cmat qpp::Gates::Z {cmat::Zero(2, 2)}
```

Pauli Sigma-Z gate.

The documentation for this class was generated from the following file:


classes/gates.h

7.17 qpp::QCircuit::GateStep Struct Reference

One step consisting only of gates/operators in the circuit.

```
#include <classes/circuits/circuits.h>
```

Collaboration diagram for qpp::QCircuit::GateStep:



Public Member Functions

• GateStep ()=default

Default constructor.

GateStep (GateType gate_type, std::size_t gate_hash, const std::vector< idx > &ctrl, const std::vector< idx > &target, const std::vector< idx > &shift={}, std::string name={})

Constructs a gate step instance.

Public Attributes

```
GateType gate_type_ = GateType::NONE
```

gate type

std::size_t gate_hash_ {}

gate hash

• std::vector< $idx > ctrl_{\{\}}$

control

std::vector< idx > target_{}{}

target where the gate is applied

std::vector< idx > shift_{}{}

shifts in CTRL gates

custom name of the step

7.17.1 Detailed Description

One step consisting only of gates/operators in the circuit.

7.17.2 Constructor & Destructor Documentation

```
7.17.2.1 GateStep() [1/2]

qpp::QCircuit::GateStep::GateStep ( ) [default]
```

Default constructor.

7.17.2.2 GateStep() [2/2]

```
qpp::QCircuit::GateStep::GateStep (
    GateType gate_type,
    std::size_t gate_hash,
    const std::vector< idx > & ctrl,
    const std::vector< idx > & target,
    const std::vector< idx > & shift = {},
    std::string name = {} ) [inline], [explicit]
```

Constructs a gate step instance.

Parameters

gate_type	Gate type
gate_hash	Hash of the quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes
name	Optional gate name

7.17.3 Member Data Documentation

```
7.17.3.1 ctrl_
std::vector<idx> qpp::QCircuit::GateStep::ctrl_ {}
control
```

```
7.17.3.2 gate_hash_
std::size_t qpp::QCircuit::GateStep::gate_hash_ {}
gate hash
7.17.3.3 gate_type_
GateType qpp::QCircuit::GateStep::gate_type_ = GateType::NONE
gate type
7.17.3.4 name
std::string qpp::QCircuit::GateStep::name_ {}
custom name of the step
7.17.3.5 shift_
std::vector<idx> qpp::QCircuit::GateStep::shift_ {}
shifts in CTRL gates
7.17.3.6 target_
std::vector<idx> qpp::QCircuit::GateStep::target_ {}
target where the gate is applied
```

The documentation for this struct was generated from the following file:

• classes/circuits/circuits.h

7.18 qpp::internal::HashEigen Class Reference

Functor for hashing Eigen expressions.

```
#include <functions.h>
```

Public Member Functions

template<typename Derived >
 std::size_t operator() (const Eigen::MatrixBase< Derived > &A) const

7.18.1 Detailed Description

Functor for hashing Eigen expressions.

7.18.2 Member Function Documentation

7.18.2.1 operator()()

The documentation for this class was generated from the following file:


· functions.h

7.19 qpp::IDisplay Class Reference

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

```
#include <classes/idisplay.h>
```

Inheritance diagram for qpp::IDisplay:



Public Member Functions

virtual ~IDisplay ()=default
 Default virtual destructor.

Private Member Functions

virtual std::ostream & display (std::ostream &os) const =0
 Must be overridden by all derived classes.

Friends

std::ostream & operator<< (std::ostream &os, const IDisplay &rhs)
 Overloads the extraction operator.

7.19.1 Detailed Description

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

This class defines friend std::ostream& operator<<(std::ostream& os, const qpp::IDisplay& rhs). The latter delegates the work to the pure private virtual function qpp::IDisplay::display() which has to be overridden by all derived classes.

7.19.2 Constructor & Destructor Documentation

```
7.19.2.1 ~IDisplay()

virtual qpp::IDisplay::~IDisplay ( ) [virtual], [default]

Default virtual destructor.
```

7.19.3 Member Function Documentation

```
7.19.3.1 display()
```

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implemented in qpp::QCircuit, qpp::QEngine, qpp::QCircuit::iterator::value_type_, qpp::Dynamic_bitset, qpp::internal::IOManipEigen, qpp::Timer< T, CLOCK_T >, qpp::internal::IOManipPointer< PointerType >, and qpp::internal::IOManipRange< InputIterator >.

7.19.4 Friends And Related Function Documentation

7.19.4.1 operator <<

Overloads the extraction operator.

Delegates the work to the virtual function qpp::IDisplay::display()

The documentation for this class was generated from the following file:


· classes/idisplay.h

7.20 qpp::IJSON Class Reference

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

```
#include <classes/idisplay.h>
```

Inheritance diagram for qpp::IJSON:



Public Member Functions

- virtual \sim IJSON ()=default
 - Default virtual destructor.
- virtual std::string to_JSON (bool enclosed_in_curly_brackets=true) const =0
 JSON representation of the derived instance, must be overridden by all derived classes.

7.20.1 Detailed Description

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

7.20.2 Constructor & Destructor Documentation

```
7.20.2.1 \simIJSON() virtual qpp::IJSON::\simIJSON ( ) [virtual], [default]
```

7.20.3 Member Function Documentation

Default virtual destructor.

JSON representation of the derived instance, must be overridden by all derived classes.

Parameters

enclosed_in_curly_brackets	If true, encloses the result in curly brackets

Implemented in qpp::QCircuit, and qpp::QEngine.

The documentation for this class was generated from the following file:


· classes/idisplay.h

7.21 qpp::ILayout Class Reference

Mandatory interface for layouts.

```
#include <classes/layouts.h>
```

Inheritance diagram for qpp::ILayout:



Public Member Functions

- virtual idx operator() (const std::vector< idx > &xs) const =0
 - Computes the index of the point represented by xs in the lattice coordinate system.
- virtual std::vector< idx > to_coordinates (idx i) const =0

Converts index to coordinates.

- virtual std::vector< idx > get_dims () const =0
 - Coordinate system dimensions.
- virtual ∼ILayout ()=default

Default virtual destructor.

7.21.1 Detailed Description

Mandatory interface for layouts.

7.21.2 Constructor & Destructor Documentation

```
7.21.2.1 ∼ILayout()
```

```
virtual qpp::ILayout::~ILayout ( ) [virtual], [default]
```

Default virtual destructor.

7.21.3 Member Function Documentation

```
7.21.3.1 get_dims()
```

```
virtual std::vector<idx> qpp::ILayout::get_dims ( ) const [pure virtual]
```

Coordinate system dimensions.

Returns

Coordinate system dimensions

Implemented in qpp::Lattice.

7.21.3.2 operator()()

Computes the index of the point represented by xs in the lattice coordinate system.

Parameters

xs | Vector of coordinates in the lattice coordinate system

Returns

Index of the point represented by xs in the lattice coordinate system

Implemented in qpp::Lattice.

7.21.3.3 to_coordinates()

```
virtual std::vector<idx> qpp::ILayout::to_coordinates ( idx \ i ) const [pure virtual]
```

Converts index to coordinates.

Parameters

i Index

Returns

coordinates of the point with index i

Implemented in qpp::Lattice.

The documentation for this class was generated from the following file:


· classes/layouts.h

7.22 qpp::Init Class Reference


const Singleton class that performs additional initializations/cleanups

#include <classes/init.h>

Inheritance diagram for qpp::Init:



Collaboration diagram for qpp::Init:



Private Member Functions

• Init ()

Additional initializations.

• ∼Init ()

Cleanups.

Friends

• class internal::Singleton< const Init >

Additional Inherited Members

7.22.1 Detailed Description

const Singleton class that performs additional initializations/cleanups

7.22.2 Constructor & Destructor Documentation

```
7.22.2.1 Init()
```

```
qpp::Init::Init ( ) [inline], [private]
```

Additional initializations.

```
7.22.2.2 ∼Init()
```

```
qpp::Init::~Init ( ) [inline], [private]
```

Cleanups.

7.22.3 Friends And Related Function Documentation

```
7.22.3.1 internal::Singleton< const Init>
```

```
friend class internal::Singleton< const Init > [friend]
```

The documentation for this class was generated from the following file:


· classes/init.h

7.23 qpp::exception::InvalidIterator Class Reference


Invalid iterator.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::InvalidIterator:



Collaboration diagram for qpp::exception::InvalidIterator:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.23.1 Detailed Description

Invalid iterator.

7.23.2 Member Function Documentation

7.23.2.1 description()

```
std::string qpp::exception::InvalidIterator::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.23.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
wnere	lext representing where the exception occurre


The documentation for this class was generated from the following file:

· classes/exception.h


7.24 qpp::internal::IOManipEigen Class Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipEigen:



Collaboration diagram for qpp::internal::IOManipEigen:



Public Member Functions

- template<typename Derived >
 IOManipEigen (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
- IOManipEigen (const cplx z, double chop=qpp::chop)

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- · cmat A_
- · double chop_

7.24.1 Constructor & Destructor Documentation

7.24.2 Member Function Documentation

```
7.24.2.1 display()
```

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.24.3 Member Data Documentation

7.24.3.1 A_

```
cmat qpp::internal::IOManipEigen::A_ [private]
```

7.24.3.2 chop_

```
double qpp::internal::IOManipEigen::chop_ [private]
```


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


7.25 qpp::internal::IOManipPointer< PointerType > Class Template Reference

```
#include <internal/classes/iomanip.h>
```

Inheritance diagram for qpp::internal::IOManipPointer< PointerType >:



Collaboration diagram for qpp::internal::IOManipPointer< PointerType >:



Public Member Functions

- IOManipPointer (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)
- IOManipPointer (const IOManipPointer &)=default
- IOManipPointer & operator= (const IOManipPointer &)=default

Private Member Functions

• std::ostream & display (std::ostream &os) const override

Must be overridden by all derived classes.

Private Attributes

- const PointerType * p_
- idx N_
- std::string separator_
- std::string start_
- std::string end_
- double chop_

7.25.1 Constructor & Destructor Documentation

7.25.1.1 IOManipPointer() [1/2]

7.25.1.2 IOManipPointer() [2/2]

7.25.2 Member Function Documentation

7.25.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.25.2.2 operator=()

7.25.3 Member Data Documentation

```
7.25.3.1 chop_
template<typename PointerType >
double qpp::internal::IOManipPointer< PointerType >::chop_ [private]
7.25.3.2 end
{\tt template}{<}{\tt typename PointerType} \,>\,
std::string qpp::internal::IOManipPointer< PointerType >::end_ [private]
7.25.3.3 N_
template<typename PointerType >
idx qpp::internal::IOManipPointer< PointerType >::N_ [private]
7.25.3.4 p_
template<typename PointerType >
const PointerType* qpp::internal::IOManipPointer< PointerType >::p_ [private]
7.25.3.5 separator_
template<typename PointerType >
std::string qpp::internal::IOManipPointer< PointerType >::separator_ [private]
7.25.3.6 start
{\tt template}{<}{\tt typename PointerType} \,>\,
std::string qpp::internal::IOManipPointer< PointerType >::start_ [private]
```


The documentation for this class was generated from the following file:

internal/classes/iomanip.h

7.26 qpp::internal::IOManipRange < InputIterator > Class Template Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipRange< InputIterator >:



Collaboration diagram for qpp::internal::IOManipRange< InputIterator >:



Public Member Functions

- IOManipRange (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)
- IOManipRange (const IOManipRange &)=default
- IOManipRange & operator= (const IOManipRange &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- · InputIterator first_
- InputIterator last_
- std::string separator_
- std::string start_
- · std::string end_
- double chop_

7.26.1 Constructor & Destructor Documentation

7.26.1.1 IOManipRange() [1/2]

7.26.1.2 IOManipRange() [2/2]

7.26.2 Member Function Documentation

7.26.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.26.2.2 operator=()

7.26.3 Member Data Documentation

```
7.26.3.1 chop_
```

```
template<typename InputIterator >
double qpp::internal::IOManipRange< InputIterator >::chop_ [private]
```

7.26.3.2 end_

```
template<typename InputIterator >
std::string qpp::internal::IOManipRange< InputIterator >::end_ [private]
```

7.26.3.3 first_

```
template<typename InputIterator >
InputIterator qpp::internal::IOManipRange< InputIterator >::first_ [private]
```

7.26.3.4 last_

```
template<typename InputIterator >
InputIterator qpp::internal::IOManipRange< InputIterator >::last_ [private]
```

7.26.3.5 separator_

```
template<typename InputIterator >
std::string qpp::internal::IOManipRange< InputIterator >::separator_ [private]
```

7.26.3.6 start_

```
template<typename InputIterator >
std::string qpp::internal::IOManipRange< InputIterator >::start_ [private]
```

The documentation for this class was generated from the following file:


• internal/classes/iomanip.h

7.27 qpp::is_complex< T > Struct Template Reference


Checks whether the type is a complex type.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_complex < T >:



Collaboration diagram for qpp::is_complex< T >:



7.27.1 Detailed Description

$$\label{template} \begin{split} & \text{template}\!<\!\text{typename T}\!> \\ & \text{struct qpp::is_complex}\!<\!\text{T}\!> \end{split}$$

Checks whether the type is a complex type.

Provides the constant member value which is equal to true, if the type is a complex type, i.e. std::complex<T>

The documentation for this struct was generated from the following file:


• traits.h

7.28 qpp::is_complex < std::complex < T > > Struct Template Reference


Checks whether the type is a complex number type, specialization for complex types.

#include <traits.h>

Inheritance diagram for qpp::is_complex< std::complex< T >>:



Collaboration diagram for qpp::is_complex < std::complex < T > >:



7.28.1 Detailed Description

```
\label{template} \begin{tabular}{ll} template < typename T > \\ struct qpp::is\_complex < std::complex < T > > \\ \end{tabular}
```

Checks whether the type is a complex number type, specialization for complex types.

The documentation for this struct was generated from the following file:


· traits.h

7.29 qpp::is_iterable < T, typename > Struct Template Reference


Checks whether *T* is compatible with an STL-like iterable container.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_iterable < T, typename > :



Collaboration diagram for qpp::is_iterable < T, typename >:



7.29.1 Detailed Description

template < typename T, typename = void > struct qpp::is_iterable < T, typename >

Checks whether T is compatible with an STL-like iterable container.

Provides the constant member *value* which is equal to *true*, if *T* is compatible with an iterable container, i.e. provides at least *begin()* and *end()* member functions and allows de-referencing. Otherwise, *value* is equal to *false*.


The documentation for this struct was generated from the following file:

- · traits.h
- 7.30 qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std :: declval < T >().end()), decltype(*(std::declval < T >().begin())) > > Struct Template Reference


Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

#include <traits.h>

Inheritance diagram for qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().begin())) > :



Collaboration diagram for qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval< T >().begin())) > :



7.30.1 Detailed Description

 $template < typename \ T > \\ struct \ qpp::is_iterable < T, \ to_void < decltype(std::declval < T > ().begin()), \ decltype(std::declval < T > ().end()), \ decltype(*(std::declval < T > ().begin())) > \\ \\ ::declval < T > ().begin())) > \\ \\$

Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

The documentation for this struct was generated from the following file:

· traits.h

7.31 qpp::is_matrix_expression < Derived > Struct Template Reference

Checks whether the type is an Eigen matrix expression.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_matrix_expression< Derived >:

```
std::is_base_of< Eigen
::MatrixBase< std::decay
< Derived >::type >, std
::decay< Derived >::type >
```

Collaboration diagram for qpp::is matrix expression< Derived >:

```
std::is_base_of< Eigen
::MatrixBase< std::decay
< Derived >::type >, std
::decay< Derived >::type >
```

7.31.1 Detailed Description

```
template < typename Derived > struct qpp::is_matrix_expression < Derived >
```

Checks whether the type is an Eigen matrix expression.

Provides the constant member *value* which is equal to *true*, if the type is an Eigen matrix expression of type *Eigen ∷MatrixBase Oerived* . Otherwise, *value* is equal to *false*.

The documentation for this struct was generated from the following file:


· traits.h

7.32 qpp::QCircuit::iterator Class Reference

Quantum circuit bound-checking (safe) iterator.

#include <classes/circuits/circuits.h>

Collaboration diagram for qpp::QCircuit::iterator:



Classes

· class value_type_

Value type class for qpp::QCircuit::iterator.

Public Types

• using difference_type = ptrdiff_t

iterator trait

• using value_type = value_type_

iterator trait

using pointer = const value_type *

iterator trait

• using reference = const value_type &

iterator trait

• using iterator_category = std::forward_iterator_tag

iterator trait

Public Member Functions

• iterator ()=default

Default constructor.

• iterator (const iterator &)=default

Default copy constructor.

• iterator & operator= (const iterator &)=default

Default copy assignment operator.

• iterator & operator++ ()

Prefix increment operator.

iterator operator++ (int)

Postfix increment operator.

```
    bool operator== (const iterator &rhs) const
Equality operator.
```

• bool operator!= (iterator rhs) const

Inequality operator.

const value_type_ & operator * () const

Safe de-referencing operator.

void set_begin_ (const QCircuit *qc)

Sets the iterator to std::begin(this)

void set_end_ (const QCircuit *qc)

Sets the iterator to std::begin(this)

Private Attributes

```
const QCircuit * qc_ {nullptr}
```

< non-owning pointer to the parent const quantum circuit

value_type_ elem_ {nullptr}

7.32.1 Detailed Description

Quantum circuit bound-checking (safe) iterator.

Note

The iterator is a const_iterator by default

7.32.2 Member Typedef Documentation

7.32.2.1 difference_type

```
using qpp::QCircuit::iterator::difference_type = ptrdiff_t
```

iterator trait

7.32.2.2 iterator_category

```
using qpp::QCircuit::iterator::iterator_category = std::forward_iterator_tag
```

iterator trait

```
7.32.2.3 pointer
using qpp::QCircuit::iterator::pointer = const value_type*
iterator trait
7.32.2.4 reference
using qpp::QCircuit::iterator::reference = const value_type&
iterator trait
7.32.2.5 value_type
using qpp::QCircuit::iterator::value_type = value_type_
iterator trait
7.32.3 Constructor & Destructor Documentation
7.32.3.1 iterator() [1/2]
qpp::QCircuit::iterator::iterator ( ) [default]
Default constructor.
7.32.3.2 iterator() [2/2]
```

Default copy constructor.

7.32.4 Member Function Documentation

qpp::QCircuit::iterator::iterator (

const iterator &) [default]

```
7.32.4.1 operator *()
```

```
const value_type_& qpp::QCircuit::iterator::operator * ( ) const [inline]
```

Safe de-referencing operator.

Returns

Constant reference to the iterator element

7.32.4.2 operator"!=()

Inequality operator.

Parameters

rhs Iterator against which the inequality is being tested

Returns

True if the iterators are not equal (bit by bit), false otherwise

```
7.32.4.3 operator++() [1/2]
```

```
iterator& qpp::QCircuit::iterator::operator++ ( ) [inline]
```

Prefix increment operator.

Returns

Reference to the current instance

```
7.32.4.4 operator++() [2/2]
```

Postfix increment operator.

Returns

Copy of the current instance before the increment

7.32.4.5 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

7.32.4.6 operator==()

Equality operator.

Parameters

rhs | Iterator against which the equality is being tested

Returns

True if the iterators are equal, false otherwise

7.32.4.7 set_begin_()

Sets the iterator to std::begin(this)

Parameters

qc | Pointer to constant quantum circuit

7.32.4.8 set_end_()

Sets the iterator to std::begin(this)

Parameters

qc Pointer to constant quantum circuit

7.32.5 Member Data Documentation

```
7.32.5.1 elem_
```

```
value_type_ qpp::QCircuit::iterator::elem_ {nullptr} [private]
```

7.32.5.2 qc_

```
const QCircuit* qpp::QCircuit::iterator::qc_ {nullptr} [private]
```

< non-owning pointer to the parent const quantum circuit

The documentation for this class was generated from the following file:


· classes/circuits/circuits.h

7.33 qpp::Lattice Class Reference


N-dimensional orthogonal lattice coordinate system.

```
#include <classes/layouts.h>
```

Inheritance diagram for qpp::Lattice:



Collaboration diagram for qpp::Lattice:



Public Member Functions

Lattice (const std::vector < idx > &dims)

Constructor.

template < class... Ts >
 Lattice (Ts... ds)

Variadic constructor.

• idx operator() (const std::vector< idx > &xs) const override

Computes the index of the point represented by xs in the lattice coordinate system.

• template<class... Ts>

idx operator() (Ts... xs) const

Computes the index of the point represented by xs in the lattice coordinate system.

• std::vector< idx > to_coordinates (idx i) const override

Converts index to lattice coordinates.

std::vector < idx > get_dims () const override

Lattice dimensions.

Private Member Functions

• idx prod_dims (idx n) const

Computes the product of the first n dimensions.

idx compute_ (const std::vector< idx > &xs, idx n) const

Computes the index of the point represented by xs in the lattice coordinate system.

Private Attributes

std::vector < idx > dims_
 lattice dimensions

7.33.1 Detailed Description

N-dimensional orthogonal lattice coordinate system.

7.33.2 Constructor & Destructor Documentation

Parameters

dims | Vector of lattice dimensions

```
7.33.2.2 Lattice() [2/2]
```

Variadic constructor.

Template Parameters

```
Ts Variadic type list
```

Parameters

```
ds Lattice dimensions
```

7.33.3 Member Function Documentation

```
7.33.3.1 compute_()
```

Computes the index of the point represented by xs in the lattice coordinate system.

Parameters

XS	Coordinates in the lattice coordinate system
n	Recursion index

Returns

Index of the point represented by xs in the lattice coordinate system

7.33.3.2 get_dims()

```
std::vector<idx> qpp::Lattice::get_dims ( ) const [inline], [override], [virtual]
```

Lattice dimensions.

Returns

Lattice dimensions

Implements qpp::ILayout.

```
7.33.3.3 operator()() [1/2]
```

Computes the index of the point represented by xs in the lattice coordinate system.

Parameters

```
xs Vector of coordinates in the lattice coordinate system
```

Returns

Index of the point represented by xs in the lattice coordinate system

Implements qpp::ILayout.

Computes the index of the point represented by xs in the lattice coordinate system.

Template Parameters

Ts	Variadic yype list	
----	--------------------	--

Parameters

```
xs Coordinates in the lattice coordinate system
```

Returns

Index of the point represented by xs in the lattice coordinate system

7.33.3.5 prod_dims()

```
idx qpp::Lattice::prod_dims (
          idx n ) const [inline], [private]
```

Computes the product of the first *n* dimensions.

Parameters

```
n Index
```

Returns

Product of the first *n* dimensions

7.33.3.6 to_coordinates()

Converts index to lattice coordinates.

Parameters

```
i Index
```

Returns

Lattice coordinates of the point with index i

Implements qpp::ILayout.

7.33.4 Member Data Documentation

```
7.33.4.1 dims_
std::vector<idx> qpp::Lattice::dims_ [private]
lattice dimensions
```

The documentation for this class was generated from the following file:

· classes/layouts.h

7.34 qpp::make_void < Ts > Struct Template Reference

```
Helper for <a href="mailto:qpp::to_void">qpp::to_void<>> alias template.</a>
```

```
#include <traits.h>
```

Public Types

· typedef void type

7.34.1 Detailed Description

```
\label{template} \begin{split} & \mathsf{template}\!<\!\mathsf{typename...} \; \mathsf{Ts}\!> \\ & \mathsf{struct} \; \mathsf{qpp::make\_void}\!<\!\; \mathsf{Ts}> \end{split}
```

Helper for qpp::to_void<>> alias template.

See also

qpp::to_void<>

7.34.2 Member Typedef Documentation

7.34.2.1 type

```
template<typename... Ts>
typedef void qpp::make_void< Ts >::type
```

The documentation for this struct was generated from the following file:


· traits.h

7.35 qpp::exception::MatrixMismatchSubsys Class Reference


Matrix mismatch subsystems exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixMismatchSubsys:



Collaboration diagram for qpp::exception::MatrixMismatchSubsys:



• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.35.1 Detailed Description

Matrix mismatch subsystems exception.

Matrix size mismatch subsystem sizes (e.g. in qpp::apply())

7.35.2 Member Function Documentation

7.35.2.1 description()

std::string qpp::exception::MatrixMismatchSubsys::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.35.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred	
-------	--	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.36 qpp::exception::MatrixNotCvector Class Reference


Matrix is not a column vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotCvector:



Collaboration diagram for qpp::exception::MatrixNotCvector:



• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.36.1 Detailed Description

Matrix is not a column vector exception.

Eigen::Matrix is not a column vector

7.36.2 Member Function Documentation

7.36.2.1 description()

std::string qpp::exception::MatrixNotCvector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.36.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.37 qpp::exception::MatrixNotRvector Class Reference


Matrix is not a row vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotRvector:



Collaboration diagram for qpp::exception::MatrixNotRvector:



• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.37.1 Detailed Description

Matrix is not a row vector exception.

Eigen::Matrix is not a row vector

7.37.2 Member Function Documentation

7.37.2.1 description()

std::string qpp::exception::MatrixNotRvector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.37.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred	
-------	--	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.38 qpp::exception::MatrixNotSquare Class Reference


Matrix is not square exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquare:



Collaboration diagram for qpp::exception::MatrixNotSquare:



• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.38.1 Detailed Description

Matrix is not square exception.

Eigen::Matrix is not a square matrix

7.38.2 Member Function Documentation

7.38.2.1 description()

std::string qpp::exception::MatrixNotSquare::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.38.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred	1
-------	--	---

The documentation for this class was generated from the following file:


· classes/exception.h

7.39 qpp::exception::MatrixNotSquareNorCvector Class Reference


Matrix is not square nor column vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorCvector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorCvector:



• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.39.1 Detailed Description

Matrix is not square nor column vector exception.

Eigen::Matrix is not a square matrix nor a column vector

7.39.2 Member Function Documentation

7.39.2.1 description()

std::string qpp::exception::MatrixNotSquareNorCvector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.39.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

The documentation for this class was generated from the following file:


· classes/exception.h

7.40 qpp::exception::MatrixNotSquareNorRvector Class Reference


Matrix is not square nor row vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorRvector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorRvector:



• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.40.1 Detailed Description

Matrix is not square nor row vector exception.

Eigen::Matrix is not a square matrix nor a row vector

7.40.2 Member Function Documentation

7.40.2.1 description()

std::string qpp::exception::MatrixNotSquareNorRvector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.40.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred	
-------	--	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.41 qpp::exception::MatrixNotSquareNorVector Class Reference


Matrix is not square nor vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorVector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorVector:



• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.41.1 Detailed Description

Matrix is not square nor vector exception.

Eigen::Matrix is not a square matrix nor a row/column vector

7.41.2 Member Function Documentation

7.41.2.1 description()

std::string qpp::exception::MatrixNotSquareNorVector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.41.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.42 qpp::exception::MatrixNotVector Class Reference


Matrix is not a vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotVector:



Collaboration diagram for qpp::exception::MatrixNotVector:



• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.42.1 Detailed Description

Matrix is not a vector exception.

Eigen::Matrix is not a row or column vector

7.42.2 Member Function Documentation

7.42.2.1 description()

std::string qpp::exception::MatrixNotVector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.42.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred	
-------	--	--

The documentation for this class was generated from the following file:


classes/exception.h

7.43 qpp::QCircuit::MeasureStep Struct Reference

One step consisting only of measurements in the circuit.

```
#include <classes/circuits/circuits.h>
```

Collaboration diagram for qpp::QCircuit::MeasureStep:



Public Member Functions

• MeasureStep ()=default

Default constructor.

MeasureStep (MeasureType measurement_type, const std::vector< std::size_t > &mats_hash, const std
 ::vector< idx > &target, idx c_reg, std::string name={})

Constructs a measurement step instance.

Public Attributes

• MeasureType measurement_type_ = MeasureType::NONE

measurement type

- std::vector< std::size_t > mats_hash_ {}
- std::vector< idx > target_{}{}

target where the measurement is applied

- idx c_reg_ {}
- std::string name_{}

custom name of the step

7.43.1 Detailed Description

One step consisting only of measurements in the circuit.

7.43.2 Constructor & Destructor Documentation

```
7.43.2.1 MeasureStep() [1/2]

qpp::QCircuit::MeasureStep::MeasureStep ( ) [default]
```

Default constructor.

7.43.2.2 MeasureStep() [2/2]

Constructs a measurement step instance.

Parameters

measurement_type	Measurement type
mats_hash	Vector of hashes of the measurement matrix/matrices
target	Target qudit indexes
c_reg	Classical register where the value of the measurement is stored
name	Optional gate name

7.43.3 Member Data Documentation

```
7.43.3.1 c_reg_
idx qpp::QCircuit::MeasureStep::c_reg_ {}
```

index of the classical register where the measurement result is being stored

```
7.43.3.2 mats_hash_
std::vector<std::size_t> qpp::QCircuit::MeasureStep::mats_hash_ {}
```

hashes of measurement matrix/matrices

7.43.3.3 measurement_type_

```
MeasureType qpp::QCircuit::MeasureStep::measurement_type_ = MeasureType::NONE
```

measurement type

7.43.3.4 name_

```
std::string qpp::QCircuit::MeasureStep::name_ {}
```

custom name of the step

7.43.3.5 target_

```
std::vector<idx> qpp::QCircuit::MeasureStep::target_ {}
```

target where the measurement is applied

The documentation for this struct was generated from the following file:


· classes/circuits/circuits.h

7.44 qpp::exception::NoCodeword Class Reference


Codeword does not exist exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::NoCodeword:



Collaboration diagram for qpp::exception::NoCodeword:



Public Member Functions

- std::string description () const override
 - Exception description.
- Exception (const std::string &where)

Constructs an exception.

7.44.1 Detailed Description

Codeword does not exist exception.

Codeword does not exist, thrown when calling qpp::Codes::codeword() with an invalid index

7.44.2 Member Function Documentation

7.44.2.1 description()

std::string qpp::exception::NoCodeword::description () const [inline], [override], [virtual]
Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.44.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.45 qpp::NoiseBase < T > Class Template Reference

Base class for all noise models, derive your particular noise model.

```
#include <classes/noise.h>
```

Collaboration diagram for qpp::NoiseBase< T >:



Public Types

• using noise_type = T

Public Member Functions

template<typename U = noise_type>
 NoiseBase (const std::vector< cmat > &Ks, typename std::enable_if< std::is_same< NoiseType::StateDependent,
 U >::value >::type *=nullptr)

Constructs a noise instance for StateDependent noise type.

• template<typename U = noise_type>

NoiseBase (const std::vector< cmat > &Ks, const std::vector< double > &probs, typename std::enable_if< std::is_same< NoiseType::StateIndependent, U >::value >::type *=nullptr)

Constructs a noise instance for StateIndependent noise type.

virtual ∼NoiseBase ()=default

Default virtual destructor.

• idx get d () const noexcept

Qudit dimension.

std::vector < cmat > get_Ks () const

Vector of noise operators.

• std::vector< double > get_probs () const

Vector of probabilities corresponding to each noise operator.

idx get_last_idx () const

Index of the last occurring noise element.

double get_last_p () const

Probability of the last occurring noise element.

cmat get_last_K () const

Last occurring noise element.

virtual cmat operator() (const cmat &state) const

Function invocation operator, applies the underlying noise model on the state vector or density matrix state.

· virtual cmat operator() (const cmat &state, idx target) const

Function invocation operator, applies the underlying noise model on qudit target of the multi-partite state vector or density matrix state.

virtual cmat operator() (const cmat &state, const std::vector < idx > &target) const

Function invocation operator, applies the underlying correlated noise model on qudits specified by target of the multipartite state vector or density matrix state.

Protected Member Functions

void compute_probs_ (const cmat &state, const std::vector < idx > &target) const

Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

• cmat compute_state_ (const cmat &state, const std::vector< idx > &target) const

Compute the resulting state after the noise was applied.

Protected Attributes

const std::vector< cmat > Ks_

Kraus operators.

std::vector< double > probs

probabilities

idx d_ {}

qudit dimension

idx i_ {}

index of the last occurring noise element

bool generated_ {false}

invoked, or if the noise is state-independent

7.45.1 Detailed Description

```
\label{eq:template} \begin{split} \text{template} &< \text{class T}> \\ \text{class qpp::NoiseBase} &< \text{T}> \end{split}
```

Base class for all noise models, derive your particular noise model.

7.45.2 Member Typedef Documentation

7.45.2.1 noise_type

```
template<class T>
using qpp::NoiseBase< T >::noise_type = T
```

7.45.3 Constructor & Destructor Documentation

7.45.3.1 NoiseBase() [1/2]

Constructs a noise instance for StateDependent noise type.

Note

SFINAEd-out for StateIndependent noise

Parameters

Ks | Vector of noise (Kraus) operators that specify the noise

7.45.3.2 NoiseBase() [2/2]

```
template<class T>
template<typename U = noise_type>
```

Constructs a noise instance for StateIndependent noise type.

Note

SFINAEd-out for StateDependent noise

Parameters

Ks	Vector of noise (Kraus) operators that specify the noise
probs	Vector of probabilities corresponding to each Kraus operator

7.45.3.3 ∼NoiseBase()

```
template<class T>
virtual qpp::NoiseBase< T >::~NoiseBase () [virtual], [default]
```

Default virtual destructor.

7.45.4 Member Function Documentation

7.45.4.1 compute_probs_()

Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

Parameters

state	State vector or density matrix
target	Qudit indexes where the noise is applied

7.45.4.2 compute_state_()

Compute the resulting state after the noise was applied.

Parameters

state	State vector or density matrix
target	Qudit indexes where the noise is applied

Returns

Resulting state after the noise was applied

7.45.4.3 get_d()

```
template<class T>
idx qpp::NoiseBase< T >::get_d ( ) const [inline], [noexcept]
```

Qudit dimension.

Returns

Qudit dimension

7.45.4.4 get_Ks()

```
template<class T>
std::vector<cmat> qpp::NoiseBase< T >::get_Ks () const [inline]
```

Vector of noise operators.

Returns

Vector of noise operators

```
7.45.4.5 get_last_idx()
```

```
template<class T>
idx qpp::NoiseBase< T >::get_last_idx ( ) const [inline]
```

Index of the last occurring noise element.

Returns

Index of the last occurring noise element

7.45.4.6 get_last_K()

```
template<class T>
cmat qpp::NoiseBase< T >::get_last_K ( ) const [inline]
```

Last occurring noise element.

Returns

Last occurring noise element

7.45.4.7 get_last_p()

```
template<class T>
double qpp::NoiseBase< T >::get_last_p ( ) const [inline]
```

Probability of the last occurring noise element.

Returns

Probability of the last occurring noise element

7.45.4.8 get_probs()

```
template<class T>
std::vector<double> qpp::NoiseBase< T >::get_probs ( ) const [inline]
```

Vector of probabilities corresponding to each noise operator.

Returns

Probability vector

7.45.4.9 operator()() [1/3]

Function invocation operator, applies the underlying noise model on the state vector or density matrix state.

Parameters

state	State vector or density matrix
-------	--------------------------------

Returns

Resulting state vector or density matrix

Function invocation operator, applies the underlying noise model on qudit *target* of the multi-partite state vector or density matrix *state*.

Parameters

state	Multi-partite state vector or density matrix
target	Qudit index where the noise is applied

Returns

Resulting state vector or density matrix

Function invocation operator, applies the underlying correlated noise model on qudits specified by *target* of the multi-partite state vector or density matrix *state*.

Parameters

state	Multi-partite state vector or density matrix
target	Qudit indexes where the correlated noise is applied

Returns

Resulting state vector or density matrix

7.45.5 Member Data Documentation

```
7.45.5.1 d_
template<class T>
idx qpp::NoiseBase< T >::d_ {} [mutable], [protected]
qudit dimension
7.45.5.2 generated_
template<class T>
bool qpp::NoiseBase< T >::generated_ {false} [mutable], [protected]
invoked, or if the noise is state-independent
set to true after compute_state_() is
7.45.5.3 i_
template<class T>
idx qpp::NoiseBase< T >::i_ {} [mutable], [protected]
index of the last occurring noise element
```

```
7.45.5.4 Ks_
```

```
template<class T>
const std::vector<cmat> qpp::NoiseBase< T >::Ks_ [protected]
```

Kraus operators.

7.45.5.5 probs_

```
template<class T>
std::vector<double> qpp::NoiseBase< T >::probs_ [mutable], [protected]
```

probabilities

The documentation for this class was generated from the following file:

· classes/noise.h

7.46 qpp::NoiseType Class Reference

Contains template tags used to specify the noise type.

```
#include <classes/noise.h>
```

Classes

· class StateDependent

Template tag, used whenever the noise is state-dependent.

· class StateIndependent

Template tag, used whenever the noise is state-independent.

7.46.1 Detailed Description

Contains template tags used to specify the noise type.

The documentation for this class was generated from the following file:


• classes/noise.h

7.47 qpp::exception::NotBipartite Class Reference


Not bi-partite exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotBipartite:



Collaboration diagram for qpp::exception::NotBipartite:



Public Member Functions

- std::string description () const override Exception description.
- Exception (const std::string &where)

 Constructs an exception.

7.47.1 Detailed Description

Not bi-partite exception.

std::vector<idx> of dimensions has size different from 2

7.47.2 Member Function Documentation

7.47.2.1 description()

```
std::string qpp::exception::NotBipartite::description ( ) const [inline], [override], [virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.47.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.48 qpp::exception::NotImplemented Class Reference


Code not yet implemented.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception::NotImplemented:$



Collaboration diagram for qpp::exception::NotImplemented:



Public Member Functions

- std::string description () const override
 - Exception description.
- Exception (const std::string &where)

Constructs an exception.

7.48.1 Detailed Description

Code not yet implemented.

7.48.2 Member Function Documentation

7.48.2.1 description()

```
std::string qpp::exception::NotImplemented::description ( ) const [inline], [override], [virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.48.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

whei	e T	ext representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.49 qpp::exception::NotQubitCvector Class Reference


Column vector is not 2 x 1 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitCvector:



Collaboration diagram for qpp::exception::NotQubitCvector:



Public Member Functions

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.49.1 Detailed Description

Column vector is not 2 x 1 exception.

Eigen::Matrix is not 2 x 1

7.49.2 Member Function Documentation

7.49.2.1 description()

```
std::string qpp::exception::NotQubitCvector::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.49.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.50 qpp::exception::NotQubitMatrix Class Reference


Matrix is not 2 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitMatrix:



Collaboration diagram for qpp::exception::NotQubitMatrix:



Public Member Functions

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.50.1 Detailed Description

Matrix is not 2 x 2 exception.

Eigen::Matrix is not 2 x 2

7.50.2 Member Function Documentation

7.50.2.1 description()

std::string qpp::exception::NotQubitMatrix::description () const [inline], [override], [virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.50.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the	e exception occurred
-----------------------------------	----------------------

The documentation for this class was generated from the following file:


· classes/exception.h

7.51 qpp::exception::NotQubitRvector Class Reference


Row vector is not 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitRvector:



Collaboration diagram for qpp::exception::NotQubitRvector:



Public Member Functions

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.51.1 Detailed Description

Row vector is not 1 x 2 exception.

Eigen::Matrix is not 1 x 2

7.51.2 Member Function Documentation

7.51.2.1 description()

```
std::string qpp::exception::NotQubitRvector::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.51.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurre	d
---	---

The documentation for this class was generated from the following file:


· classes/exception.h

7.52 qpp::exception::NotQubitSubsys Class Reference


Subsystems are not qubits exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitSubsys:



Collaboration diagram for qpp::exception::NotQubitSubsys:



Public Member Functions

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.52.1 Detailed Description

Subsystems are not qubits exception.

Subsystems are not 2-dimensional (qubits)

7.52.2 Member Function Documentation

7.52.2.1 description()

std::string qpp::exception::NotQubitSubsys::description () const [inline], [override], [virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.52.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the	e exception occurred
-----------------------------------	----------------------

The documentation for this class was generated from the following file:


· classes/exception.h

7.53 qpp::exception::NotQubitVector Class Reference


Vector is not 2 x 1 nor 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitVector:



Collaboration diagram for qpp::exception::NotQubitVector:



Public Member Functions

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.53.1 Detailed Description

Vector is not 2 x 1 nor 1 x 2 exception.

Eigen::Matrix is not 2 x 1 nor 1 x 2

7.53.2 Member Function Documentation

7.53.2.1 description()

std::string qpp::exception::NotQubitVector::description () const [inline], [override], [virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.53.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.54 qpp::exception::OutOfRange Class Reference


Argument out of range exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::OutOfRange:



Collaboration diagram for qpp::exception::OutOfRange:



Public Member Functions

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.54.1 Detailed Description

Argument out of range exception.

Argument out of range

7.54.2 Member Function Documentation

7.54.2.1 description()

```
std::string qpp::exception::OutOfRange::description ( ) const [inline], [override], [virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.54.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.55 qpp::exception::PermInvalid Class Reference


Invalid permutation exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermInvalid:



Collaboration diagram for qpp::exception::PermInvalid:



Public Member Functions

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.55.1 Detailed Description

Invalid permutation exception.

std::vector<idx> does note represent a valid permutation

7.55.2 Member Function Documentation

7.55.2.1 description()

```
std::string qpp::exception::PermInvalid::description ( ) const [inline], [override], [virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.55.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the	e exception occurred
-----------------------------------	----------------------

The documentation for this class was generated from the following file:


· classes/exception.h

7.56 qpp::exception::PermMismatchDims Class Reference


Permutation mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermMismatchDims:



Collaboration diagram for qpp::exception::PermMismatchDims:



Public Member Functions

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.56.1 Detailed Description

Permutation mismatch dimensions exception.

Size of the std::vector<idx> representing the permutation is different from the size of the std::vector<idx> of dimensions

7.56.2 Member Function Documentation

7.56.2.1 description()

```
std::string qpp::exception::PermMismatchDims::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.56.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.57 qpp::QCircuit Class Reference


Quantum circuit description.

#include <classes/circuits/circuits.h>

Inheritance diagram for qpp::QCircuit:



Collaboration diagram for qpp::QCircuit:



Classes

• struct GateStep

One step consisting only of gates/operators in the circuit.

· class iterator

Quantum circuit bound-checking (safe) iterator.

struct MeasureStep

One step consisting only of measurements in the circuit.

Public Types

enum GateType {
 GateType::NONE, GateType::SINGLE, GateType::TWO, GateType::THREE,
 GateType::CUSTOM, GateType::FAN, GateType::SINGLE_CTRL_SINGLE_TARGET, GateType::SINGLE_CTRL_MULTIPLE_
 GateType::MULTIPLE_CTRL_SINGLE_TARGET,
 GateType::CUSTOM_CTRL, GateType::SINGLE_cCTRL_SINGLE_TARGET,
 GateType::SINGLE_cCTRL_MULTIPLE_TARGET,
 GateType::MULTIPLE_cCTRL_MULTIPLE_TARGET,
 GateType::MULTIPLE_cCTRL_MULTIPLE_TARGET,
 GateType::MULTIPLE_cCTRL_MULTIPLE_TARGET,
 GateType::CUSTOM_cCTRL }
 Type of gate being executed in a gate step.

enum MeasureType {

MeasureType::MEASURE_Z, MeasureType::MEASURE_Z_MANY, MeasureType::MEASURE_V, MeasureType::MEASURE_V_MANY }

Type of measurement being executed in a measurement step.

enum StepType { StepType::NONE, StepType::GATE, StepType::MEASUREMENT, StepType::NOP }

Types of each step in the quantum circuit.

· using const iterator = iterator

both iterators are const_iterators

Public Member Functions

· iterator begin ()

Iterator to the first element.

· const iterator begin () const noexcept

Constant iterator to the first element.

· const iterator cbegin () const noexcept

Constant iterator to the first element.

• iterator end ()

Iterator to the next to the last element.

const_iterator end () const noexcept

Constant iterator to the next to the last element.

const_iterator cend () const noexcept

Constant iterator to the next to the last element.

QCircuit (idx nq, idx nc=0, idx d=2, std::string name={})

Constructs a quantum circuit.

virtual ~QCircuit ()=default

Default virtual destructor.

• idx get_nq () const noexcept

Total number of qudits in the circuit.

• idx get_nc () const noexcept

Total number of classical dits in the circuit.

• idx get_d () const noexcept

Dimension of the comprising qudits.

• std::string get_name () const

Quantum circuit name.

· idx get measured (idx i) const

Check whether qudit i was already measured.

std::vector< idx > get measured () const

Vector of already measured qudit indexes.

std::vector< idx > get_non_measured () const

Vector of non-measured qudit indexes.

idx get_gate_count (const std::string &name={}) const

Quantum circuit gate count.

idx get_depth (const std::string &name={}) const

Quantum circuit depth.

idx get_measurement_count () const noexcept

Quantum circuit total measurement count.

• idx get measurement count (const std::string &name) const

Quantum circuit measurement count.

idx get_step_count () const noexcept

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

· idx get nop count () const

No-op count.

QCircuit & add_qudit (idx n=1, idx i=-1)

Adds n additional qudits before qudit i (by default adds them at the end)

QCircuit & add_dit (idx n=1, idx i=-1)

Adds n additional classical dits before dit i (by default adds them at the end)

QCircuit & gate (const cmat &U, idx i, std::string name={})

Applies the single qudit gate U on single qudit i.

QCircuit & gate (const cmat &U, idx i, idx j, std::string name={})

Applies the two qudit gate U on qudits i and j.

• QCircuit & gate (const cmat &U, idx i, idx j, idx k, std::string name={})

Applies the three qudit gate U on qudits i, j and k.

QCircuit & gate_fan (const cmat &U, const std::vector< idx > &target, std::string name={})

Applies the single qudit gate U on every qudit listed in target.

QCircuit & gate_fan (const cmat &U, const std::initializer_list < idx > &target, std::string name={})

Applies the single qudit gate U on every qudit listed in target.

QCircuit & gate_fan (const cmat &U, std::string name={})

Applies the single qudit gate U on all of the remaining non-measured qudits.

QCircuit & gate_custom (const cmat &U, const std::vector< idx > &target, std::string name={})

Jointly applies the custom multiple qudit gate U on the qudit indexes specified by target.

QCircuit & QFT (const std::vector < idx > &target, bool swap=true)

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & QFT (const std::initializer_list< idx > &target, bool swap=true)

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & QFT (bool swap=true)

Applies the quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

QCircuit & TFQ (const std::vector < idx > &target, bool swap QPP_UNUSED_=true)

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & TFQ (const std::initializer_list< idx > &target, bool swap=true)

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & TFQ (bool swap=true)

Applies the inverse quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

QCircuit & CTRL (const cmat &U, idx ctrl, idx target, std::string name={})

Applies the single qudit controlled gate U with control qudit ctrl and target qudit target.

QCircuit & CTRL (const cmat &U, idx ctrl, const std::vector < idx > &target, std::string name={})

Applies the single qudit controlled gate U with control qudit ctrl on every qudit listed in target.

QCircuit & CTRL (const cmat &U, const std::vector < idx > &ctrl, idx target, std::string name={})

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on the target qudit target.

QCircuit & CTRL (const cmat &U, const std::vector < idx > &ctrl, const std::vector < idx > &target, std::string name={})

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on every qudit listed in target.

QCircuit & CTRL_custom (const cmat &U, const std::vector < idx > &ctrl, const std::vector < idx > &target, std::string name={})

Jointly applies the custom multiple-qudit controlled gate U with multiple control qudits listed in ctrl on the qudit indexes specified by target.

• QCircuit & cCTRL (const cmat &U, idx ctrl_dit, idx target, idx shift=0, std::string name={})

Applies the single qubit controlled gate U with classical control dit ctrl and target qudit target.

QCircuit & cCTRL (const cmat &U, idx ctrl_dit, const std::vector< idx > &target, idx shift=0, std::string name={})

Applies the single qudit controlled gate U with classical control dit ctrl on every qudit listed in target.

QCircuit & cCTRL (const cmat &U, const std::vector< idx > &ctrl_dits, idx target, const std::vector< idx > &shift={}, std::string name={})

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on the target qudit target.

QCircuit & cCTRL (const cmat &U, const std::vector< idx > &ctrl_dits, const std::vector< idx > &target, const std::vector< idx > &shift={}, std::string name={})

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on every qudit listed in target.

QCircuit & cCTRL_custom (const cmat &U, const std::vector< idx > &ctrl_dits, const std::vector< idx > &target, const std::vector< idx > &shift={}, std::string name={})

Jointly applies the custom multiple-qudit controlled gate U with multiple classical control dits listed in ctrl on the qudit indexes specified by target.

QCircuit & measureZ (idx target, idx c_reg, std::string name={})

Measurement of single qudit in the computational basis (Z-basis)

QCircuit & measureZ (const std::vector < idx > &target, idx c reg, std::string name={})

Measurement of multiple qudit in the computational basis (Z-basis)

• QCircuit & measureV (const cmat &V, idx target, idx c_reg, std::string name={})

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

QCircuit & measureV (const cmat &V, const std::vector < idx > &target, idx c reg, std::string name={})

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

• QCircuit & nop ()

No operation (no-op)

· QCircuit & replicate (idx n)

Replicates the circuit, in place.

QCircuit & add_circuit (QCircuit other, bigint pos_qudit, idx pos_dit=-1)

Appends a quantum circuit description to the current one.

• QCircuit & kron (const QCircuit &qc)

Kronecker product with another quantum circuit description, in place.

QCircuit & adjoint ()

Adjoint quantum circuit description, in place.

• std::string to_JSON (bool enclosed_in_curly_brackets=true) const override

qpp::/JSON::to_JSON() override

Private Member Functions

void add_hash_ (const cmat &U, std::size_t hashU)

Adds matrix to the hash table.

const std::vector< MeasureStep > & get_measurements_ () const noexcept

Vector of qpp::QCircuit::MeasureStep.

const std::vector< GateStep > & get_gates_() const noexcept

Vector of qpp::QCircuit::GateStep.

const std::unordered_map< std::size_t, cmat > & get_cmat_hash_tbl_ () const noexcept

Hash table with the matrices used in the circuit.

std::ostream & display (std::ostream &os) const override

qpp::IDisplay::display() override

Private Attributes

```
idx nq
     number of qudits
• idx nc_
     number of classical "dits"
idx d
     qudit dimension

    std::string name

     optional circuit name

    std::vector< bool > measured_

     keeps track of the measured qudits
std::unordered_map< std::size_t, cmat > cmat_hash_tbl_{}{}

    std::unordered map< std::string, idx > count {}

     gate counts

    std::unordered_map< std::string, idx > measurement_count_{}{}

     measurement counts
std::vector< GateStep > gates_{}{}
     gates
std::vector< MeasureStep > measurements_{}{}
     measurements
std::vector< StepType > step_types_{}
     type of each step
```

Friends

- class QEngine
- std::ostream & operator<< (std::ostream &os, const GateType &gate_type)

Extraction operator overload for qpp::QCircuit::GateType enum class.

std::ostream & operator<< (std::ostream &os, const GateStep &gate_step)

Extraction operator overload for qpp::QCircuit::GateStep class.

std::ostream & operator<< (std::ostream &os, const MeasureType &measure_type)

Extraction operator overload for qpp::QCircuit::MeasureType enum class.

std::ostream & operator<< (std::ostream &os, const MeasureStep &measure_step)

Extraction operator overload for qpp::QCircuit::MeasureStep class.

QCircuit adjoint (QCircuit qc)

Adjoint quantum circuit description.

• QCircuit kron (const QCircuit &qc1, const QCircuit &qc2)

Kronecker product between two quantum circuit descriptions.

QCircuit replicate (QCircuit qc, idx n)

Replicates the circuit.

• QCircuit add_circuit (QCircuit qc1, const QCircuit &qc2, bigint pos_qudit, idx pos_dit=-1)

Appends a quantum circuit description to another one.

7.57.1 Detailed Description

Quantum circuit description.

See also

qpp::QEngine

7.57.2 Member Typedef Documentation

7.57.2.1 const_iterator

```
using qpp::QCircuit::const_iterator = iterator
```

both iterators are const_iterators

7.57.3 Member Enumeration Documentation

7.57.3.1 GateType

```
enum qpp::QCircuit::GateType [strong]
```

Type of gate being executed in a gate step.

Enumerator

NONE	represents no gate
SINGLE	unitary gate on a single qudit
TWO	unitary gate on 2 qudits
THREE	unitary gate on 3 qudits
CUSTOM	custom gate on multiple qudits
FAN	same unitary gate on multiple qudits
SINGLE_CTRL_SINGLE_TARGET	one control and one target controlled 1 qudit unitary gate with
SINGLE_CTRL_MULTIPLE_TARGET	one control and multiple targets controlled 1 qudit unitary gate with
MULTIPLE_CTRL_SINGLE_TARGET	multiple controls and single target controlled 1 qudit unitary gate with
MULTIPLE_CTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with multiple controls and multiple targets
CUSTOM_CTRL	and multiple targets custom controlled gate with multiple controls
SINGLE_cCTRL_SINGLE_TARGET	one classical control and one target controlled 1 qudit unitary gate with
SINGLE_cCTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with one classical control and multiple targets
MULTIPLE_cCTRL_SINGLE_TARGET	controlled 1 qudit unitary gate with multiple classical controls and single target
MULTIPLE_cCTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with multiple classical controls and multiple targets
CUSTOM_cCTRL	controls and multiple targets custom controlled gate with multiple classical

7.57.3.2 MeasureType

```
enum qpp::QCircuit::MeasureType [strong]
```

Type of measurement being executed in a measurement step.

Enumerator

NONE	represents no measurement	
MEASURE_Z	Z measurement of single qudit.	
MEASURE_Z_MANY	Z measurement of multiple qudit.	
MEASURE_V	measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix $\it V$	
MEASURE_V_MANY	joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified	

7.57.3.3 StepType

```
enum qpp::QCircuit::StepType [strong]
```

Types of each step in the quantum circuit.

Enumerator

NONE	represents no step
GATE	quantum gate(s)
MEASUREMENT	measurement
NOP	no-op

7.57.4 Constructor & Destructor Documentation

7.57.4.1 QCircuit()

```
qpp::QCircuit::QCircuit (
    idx nq,
    idx nc = 0,
    idx d = 2,
    std::string name = {} ) [inline], [explicit]
```

Constructs a quantum circuit.

Note

The measurement results can only be stored in the classical dits of which number is specified by nc

Parameters

nq	Number of qbits	
nc	Number of classical dits (optional)	
d	Subsystem dimensions (optional, default is qubit, i.e. $d = 2$)	
name	Circuit name (optional)	

7.57.4.2 ~QCircuit()

```
virtual qpp::QCircuit::~QCircuit ( ) [virtual], [default]
```

Default virtual destructor.

7.57.5 Member Function Documentation

7.57.5.1 add_circuit()

Appends a quantum circuit description to the current one.

Note

If qudit indexes of the added quantum circuit description do not totally overlap with the indexes of the current quantum circuit description, then the required number of additional qudits are automatically added to the current quantum circuit description

Parameters

other	Quantum circuit description
pos_qudit	The index of the first qudit of <i>other</i> quantum circuit description relative to the index of the first qudit of the current quantum circuit description, with the rest following in order. If negative or greater than the total number of qudits of the current quantum circuit description, then the required number of additional qudits are automatically added to the current quantum circuit description.
pos_dit	The first classical dit of <i>other</i> is inserted before the <i>pos_dit</i> classical dit index of the current quantum circuit description (in the classical dits array), the rest following in order. By default, insertion is performed at the end.

Returns

Reference to the current instance

7.57.5.2 add_dit()

```
QCircuit& qpp::QCircuit::add_dit (
    idx n = 1,
    idx i = -1 ) [inline]
```

Adds *n* additional classical dits before dit *i* (by default adds them at the end)

Note

Classical dits with indexes greater or equal than the newly inserted ones have their indexes automatically incremented

Parameters

n	Number of classical dits
i	Classical dit index

Returns

Reference to the current instance

7.57.5.3 add_hash_()

Adds matrix to the hash table.

Note

Throws if a hash collision is detected., i.e., if two different matrices have the same hash

Parameters

U	Complex matrix
hashU	Hash value of U

7.57.5.4 add_qudit()

```
QCircuit& qpp::QCircuit::add_qudit (
    idx n = 1,
    idx i = -1) [inline]
```

Adds *n* additional qudits before qudit *i* (by default adds them at the end)

Note

Qudits with indexes greater or equal than the newly inserted ones have their indexes automatically incremented

Parameters

n	Number of qudits
i	Qudit index

Returns

Reference to the current instance

7.57.5.5 adjoint()

```
QCircuit& qpp::QCircuit::adjoint ( ) [inline]
```

Adjoint quantum circuit description, in place.

Returns

Reference to the current instance

```
7.57.5.6 begin() [1/2]
```

```
iterator qpp::QCircuit::begin ( ) [inline]
```

Iterator to the first element.

Returns

Iterator to the first element

```
7.57.5.7 begin() [2/2]
```

```
const_iterator qpp::QCircuit::begin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

7.57.5.8 cbegin()

```
const_iterator qpp::QCircuit::cbegin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

7.57.5.9 cCTRL() [1/4]

Applies the single qubit controlled gate U with classical control dit ctrl and target qudit target.

Parameters

U	Single qudit quantum gate	
ctrl_dit	Classical control dit index	
target	Target qudit index	
shift	Performs the control as if the ctrl_dit classical dit was incremented by shift	
name Optional gate name		

Returns

Reference to the current instance

7.57.5.10 cCTRL() [2/4]

Applies the single qudit controlled gate *U* with classical control dit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the
	classical control dits
shift	Performs the control as if the ctrl_dit classical dit was incremented by shift same as the size of
	ctrl_dits.
name	Optional gate name

Returns

Reference to the current instance

```
7.57.5.11 cCTRL() [3/4]
```

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on the target qudit target.

Parameters

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit index
shift	Performs the control as if the <i>ctrl_dits</i> classical dits were component-wise incremented by <i>shift</i> . The size of <i>shift</i> must be the same as the size of <i>ctrl_dits</i> .
name	Optional gate name

Returns

Reference to the current instance

```
7.57.5.12 cCTRL() [4/4]
```

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the classical control dits
shift	Performs the control as if the <i>ctrl_dits</i> classical dits were component-wise incremented by <i>shift</i> . The size of <i>shift</i> must be the same as the size of <i>ctrl_dits</i> .
name	Optional gate name

Returns

Reference to the current instance

7.57.5.13 cCTRL_custom()

Jointly applies the custom multiple-qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the qudit indexes specified by *target*.

Parameters

U	Multiple-qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit indexes where the gate U is applied depending on the values of the classical control dits
shift	Performs the control as if the <i>ctrl_dits</i> classical dits were component-wise incremented by <i>shift</i> . The size of <i>shift</i> must be the same as the size of <i>ctrl_dits</i> .
name	Optional gate name

Returns

Reference to the current instance

```
7.57.5.14 cend()
```

```
const_iterator qpp::QCircuit::cend ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

Returns

Constant iterator to the next to the last element

```
7.57.5.15 CTRL() [1/4]
```

Applies the single qudit controlled gate *U* with control qudit *ctrl* and target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.57.5.16 CTRL() [2/4]
```

Applies the single qudit controlled gate *U* with control qudit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.57.5.18 CTRL() [4/4]
```

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate	
ctrl	Control qudit indexes	
target	Target qudit indexes; the gate <i>U</i> is applied on every one of them depending on the values of the control qudits	
name	Optional gate name	

Returns

Reference to the current instance

7.57.5.19 CTRL_custom()

Jointly applies the custom multiple-qudit controlled gate U with multiple control qudits listed in ctrl on the qudit indexes specified by target.

Parameters

U	Multiple-qudit quantum gate	
ctrl	Control qudit indexes	
target	Target qudit indexes where the gate U is applied depending on the values of the control qudits	
name	Optional gate name	

Returns

Reference to the current instance

7.57.5.20 display()

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the quantum circuit

Parameters

	os	Output stream passed by reference
--	----	-----------------------------------

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.57.5.21 end() [1/2]
```

iterator qpp::QCircuit::end () [inline]

Iterator to the next to the last element.

Returns

Iterator to the next to the last element

```
7.57.5.22 end() [2/2]
const_iterator qpp::QCircuit::end ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

Returns

Constant iterator to the next to the last element

Applies the single qudit gate *U* on single qudit *i*.

Parameters

U	Single qudit quantum gate
i	Qudit index
name Optional gate name	

Returns

Reference to the current instance

Applies the two qudit gate *U* on qudits *i* and *j*.

Parameters

U	Two qudit quantum gate
i	Qudit index
j	Qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the three qudit gate U on qudits i, j and k.

Parameters

U	Three qudit quantum gate
i	Qudit index
j	Qudit index
k	Qudit index
name	Optional gate name

Returns

Reference to the current instance

7.57.5.26 gate_custom()

Jointly applies the custom multiple qudit gate *U* on the qudit indexes specified by *target*.

Parameters

U	Multiple qudit quantum gate	
target	Subsystem indexes where the gate <i>U</i> is applied	
name	Optional gate name	

Returns

Reference to the current instance

```
7.57.5.27 gate_fan() [1/3]
```

Applies the single qudit gate *U* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
target	Target qudit indexes; the gate <i>U</i> is applied on every one of them
name	Optional gate name

Returns

Reference to the current instance

7.57.5.28 gate_fan() [2/3]

Applies the single qudit gate *U* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
target	Target qudit indexes; the gate <i>U</i> is applied on every one of them
name	Optional gate name

Returns

Reference to the current instance

```
7.57.5.29 gate_fan() [3/3]
```

Applies the single qudit gate *U* on all of the remaining non-measured qudits.

Parameters

U	Single qudit quantum gate
name	Optional gate name

Returns

Reference to the current instance

```
7.57.5.30 get_cmat_hash_tbl_()
```

```
const std::unordered_map<std::size_t, cmat>& qpp::QCircuit::get_cmat_hash_tbl_ ( ) const
[inline], [private], [noexcept]
```

Hash table with the matrices used in the circuit.

Returns

Hash table with the matrices used in the circuit

```
7.57.5.31 get_d()
```

```
idx qpp::QCircuit::get_d ( ) const [inline], [noexcept]
```

Dimension of the comprising qudits.

Returns

Qudit dimension

7.57.5.32 get_depth()

Quantum circuit depth.

Note

If name is empty (default), returns the total depth of the circuit

Parameters

na	me	Gate/measurement name	(optional)
----	----	-----------------------	------------

Returns

Gate/measurement depth

7.57.5.33 get_gate_count()

Quantum circuit gate count.

Note

If name is empty (default), returns the total gate count of the circuit

Parameters

name	Gate name ((ontional)
Hairie	Gate Harrie	(Optional)

```
Returns
```

Gate count

```
7.57.5.34 get_gates_()
const std::vector<GateStep>& qpp::QCircuit::get_gates_ ( ) const [inline], [private], [noexcept]
Vector of qpp::QCircuit::GateStep.
```

Returns

Vector of qpp::QCircuit::GateStep

```
7.57.5.35 get_measured() [1/2] idx qpp::QCircuit::get_measured ( idx i ) const [inline]
```

Check whether qudit *i* was already measured.

Parameters

i Qudit index

Returns

True if qudit i was already measured, false othwewise

```
7.57.5.36 get_measured() [2/2]
std::vector<idx> qpp::QCircuit::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

```
7.57.5.37 get_measurement_count() [1/2]
idx qpp::QCircuit::get_measurement_count ( ) const [inline], [noexcept]
Quantum circuit total measurement count.
```

Returns

Total measurement count

Quantum circuit measurement count.

Parameters

leasurement name	name
------------------	------

Returns

Measurement count

```
7.57.5.39 get_measurements_()
```

```
const std::vector<MeasureStep>& qpp::QCircuit::get_measurements_ ( ) const [inline], [private],
[noexcept]
```

Vector of qpp::QCircuit::MeasureStep.

Returns

Vector of qpp::QCircuit::MeasureStep

```
7.57.5.40 get_name()
```

```
std::string qpp::QCircuit::get_name ( ) const [inline]
```

Quantum circuit name.

Returns

Quantum circuit name

```
7.57.5.41 get_nc()
```

```
idx qpp::QCircuit::get_nc ( ) const [inline], [noexcept]
```

Total number of classical dits in the circuit.

Returns

Total number of classical dits

```
7.57.5.42 get_non_measured()
```

```
std::vector<idx> qpp::QCircuit::get_non_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

Returns

Vector of non-measured qudit indexes

```
7.57.5.43 get_nop_count()
```

```
idx qpp::QCircuit::get_nop_count ( ) const [inline]
```

No-op count.

Returns

No-op count

```
7.57.5.44 get_nq()
```

```
idx qpp::QCircuit::get_nq ( ) const [inline], [noexcept]
```

Total number of qudits in the circuit.

Returns

Total number of qudits

```
7.57.5.45 get_step_count()
```

```
idx qpp::QCircuit::get_step_count ( ) const [inline], [noexcept]
```

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

Returns

Total (gates + measurements) count

7.57.5.46 kron()

Kronecker product with another quantum circuit description, in place.

Parameters

qc Quantum circuit description

Returns

Reference to the current instance

7.57.5.47 measureV() [1/2]

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V	
target	Qudit index	
c_reg	Classical register where the value of the measurement is stored	
name	Optional measurement name	

Returns

Reference to the current instance

7.57.5.48 measureV() [2/2]

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix *V*.

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V	
target	Target qudit indexes that are jointly measured	
c_reg	Classical register where the value of the measurement is stored	
name	Optional measurement name	

Returns

Reference to the current instance

Measurement of single qudit in the computational basis (Z-basis)

Parameters

target	Qudit index
c_reg	Classical register where the value of the measurement is being stored
name	Optional measurement name, default is "mZ"

Returns

Reference to the current instance

```
7.57.5.50 measureZ() [2/2]
```

Measurement of multiple qudit in the computational basis (Z-basis)

Parameters

target	Target qudit indexes that are measured
c_reg	Classical register where the value of the measurement is being stored, as a decimal representation of the binary string representing the measurement, with the most significant dit on the left (corresponding to the first qudit that is being measured)
name	Optional measurement name, default is "mZ"

Returns

Reference to the current instance

```
7.57.5.51 nop()
```

```
QCircuit& qpp::QCircuit::nop ( ) [inline]
```

No operation (no-op)

Note

If the underlying step is executed on a noisy engine, then noise acts before it

Returns

Reference to the current instance

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

bool swap = true) [inline]

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

Applies the quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

Parameters

```
swap Swaps the qubits at the end (true by default)
```

Returns

Reference to the current instance

7.57.5.55 replicate()

Replicates the circuit, in place.

Note

The circuit should not contain any measurements when invoking this member function

Parameters

```
n Number of repetitions. If n == 1, returns the original circuit.
```

Returns

Reference to the current instance



Parameters

target	Subsystem indexes where the inverse quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

```
7.57.5.57 TFQ() [2/3]
```

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the inverse quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

```
7.57.5.58 TFQ() [3/3]
```

Applies the inverse quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

Parameters

swap	Swaps the qubits at the end (true by default)
------	---

Returns

Reference to the current instance

```
7.57.5.59 to_JSON()
```

qpp::IJSON::to_JSON() override

Displays the quantum circuit in JSON format

Parameters

enclosed_in_curly_brackets	If true, encloses the result in curly brackets
----------------------------	--

Returns

String containing the JSON representation of the quantum circuit

Implements qpp::IJSON.

7.57.6 Friends And Related Function Documentation

7.57.6.1 add_circuit

Appends a quantum circuit description to another one.

Note

If qudit indexes of the second quantum circuit description do not totally overlap with the indexes of the first quantum circuit description, then the required number of additional qudits are automatically added to the output quantum circuit description

Parameters

qc1	Quantum circuit description
qc2	Quantum circuit description
pos_qudit	The index of the first qudit of <i>qc2</i> quantum circuit description relative to the index of the first qudit of the <i>qc1</i> quantum circuit description, with the rest following in order. If negative or greater than the total number of qudits of <i>qc1</i> , then the required number of additional qudits are automatically added to the output quantum circuit description.
pos_dit	The first classical dit of <i>qc2</i> quantum circuit description is inserted before the <i>pos_dit</i> classical dit index of <i>qc1</i> quantum circuit description (in the classical dits array), the rest following in order. By default, insertion is performed at the end.

Returns

Combined quantum circuit description

7.57.6.2 adjoint

Adjoint quantum circuit description.

Parameters

```
qc Quantum circuit description
```

Returns

Adjoint quantum circuit description

7.57.6.3 kron

Kronecker product between two quantum circuit descriptions.

Parameters

qc1	Quantum circuit description
qc2	Quantum circuit description

Returns

Quantum circuit description of the Kronecker product of qc1 with qc2

Extraction operator overload for qpp::QCircuit::GateType enum class.

Parameters

os	Output stream
gate_type	qpp::QCircuit::GateType enum class

Returns

Output stream

Extraction operator overload for qpp::QCircuit::GateStep class.

Parameters

os	Output stream
gate_step	qpp::QCircuit::GateStep class

Returns

Output stream

Extraction operator overload for qpp::QCircuit::MeasureType enum class.

Parameters

os	Output stream
measure_type	qpp::QCircuit::MeasureType enum class

Returns

Output stream

Extraction operator overload for qpp::QCircuit::MeasureStep class.

Parameters

os	Output stream
measure_step	qpp::QCircuit::MeasureStep enum class

Returns

Output stream

7.57.6.8 QEngine

```
friend class QEngine [friend]
```

7.57.6.9 replicate

Replicates the circuit.

Note

The circuit should not contain any measurements when invoking this function

Parameters

qc	Quantum circuit description
n	Number of repetitions. If $n == 1$, returns the original circuit.

Returns

Reference to the current instance

7.57.7 Member Data Documentation

```
7.57.7.1 cmat_hash_tbl_
std::unordered_map<std::size_t, cmat> qpp::QCircuit::cmat_hash_tbl_ {} [private]
hash table with the matrices used in the circuit, with [Key = std::size_t, Value = cmat]
7.57.7.2 count_
std::unordered_map<std::string, idx> qpp::QCircuit::count_ {} [private]
gate counts
7.57.7.3 d_
idx qpp::QCircuit::d_ [private]
qudit dimension
7.57.7.4 gates_
std::vector<GateStep> qpp::QCircuit::gates_ {} [private]
gates
7.57.7.5 measured_
std::vector<bool> qpp::QCircuit::measured_ [private]
keeps track of the measured qudits
7.57.7.6 measurement_count_
std::unordered_map<std::string, idx> qpp::QCircuit::measurement_count_ {} [private]
measurement counts
```

```
7.57.7.7 measurements_
std::vector<MeasureStep> qpp::QCircuit::measurements_ {} [private]
measurements
7.57.7.8 name_
std::string qpp::QCircuit::name_ [private]
optional circuit name
7.57.7.9 nc_
idx qpp::QCircuit::nc_ [private]
number of classical "dits"
7.57.7.10 nq_
idx qpp::QCircuit::nq_ [private]
number of qudits
7.57.7.11 step_types_
std::vector<StepType> qpp::QCircuit::step_types_ {} [private]
type of each step
The documentation for this class was generated from the following file:
```

Generated by Doxygen


· classes/circuits/circuits.h

7.58 qpp::QEngine Class Reference


Quantum circuit engine, executes qpp::QCircuit.

#include <classes/circuits/engines.h>

Inheritance diagram for qpp::QEngine:



Collaboration diagram for qpp::QEngine:



Classes

· class state_

Current state of the engine.

Public Member Functions

QEngine (const QCircuit &qc)

Constructs a quantum engine out of a quantum circuit.

QEngine (const QEngine &)=default

Default copy constructor.

QEngine & operator= (const QEngine &)=default

Default copy assignment operator.

• QEngine (QCircuit &&)=delete

Disables rvalue QCircuit.

virtual ~QEngine ()=default

Default virtual destructor.

ket get_psi () const

Underlying quantum state.

std::vector < idx > get_dits () const

Vector with the values of the underlying classical dits.

idx get_dit (idx i) const

Value of the classical dit at position i.

std::vector< double > get_probs () const

Vector of underlying measurement outcome probabilities.

• bool get_measured (idx i) const

Check whether qudit i was already measured.

std::vector< idx > get_measured () const

Vector of already measured qudit indexes.

std::vector< idx > get_non_measured () const

Vector of non-measured gudit indexes.

const QCircuit & get_circuit () const noexcept

Quantum circuit.

• const std::map< std::string, idx, internal::EqualSameSizeStringDits > & get_stats () const

Measurement statistics for multiple runs.

QEngine & set_dit (idx i, idx value)

Sets the classical dit at position i.

QEngine & set_psi (const ket &psi)

Sets the underlying quantum state to psi.

QEngine & reset_stats ()

Resets the collected measurement statistics hash table.

• void reset ()

Resets the engine.

• virtual void execute (const QCircuit::iterator::value_type &elem)

Executes one step in the quantum circuit.

void execute (const QCircuit::iterator &it)

Executes one step in the quantum circuit.

void execute (idx reps=1, bool clear_stats=true)

Executes the entire quantum circuit.

std::string to_JSON (bool enclosed_in_curly_brackets=true) const override

qpp::IJSON::to_JSON() override

Protected Member Functions

void set_measured_ (idx i)

Marks qudit i as measured then re-label accordingly the remaining non-measured qudits.

std::vector< idx > get_relative_pos_ (std::vector< idx > v)

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

Protected Attributes

```
    const QCircuit * qc_
        pointer to constant quantum circuit
    struct qpp::QEngine::state_ st_
        current state of the engine
    std::map< std::string, idx, internal::EqualSameSizeStringDits > stats_
        measurement statistics for multiple runs
```

Private Member Functions

```
    std::ostream & display (std::ostream &os) const override

        qpp::IDisplay::display() override
```

7.58.1 Detailed Description

Quantum circuit engine, executes qpp::QCircuit.

See also

qpp::QCircuit

7.58.2 Constructor & Destructor Documentation

Constructs a quantum engine out of a quantum circuit.

Note

The quantum circuit must be an Ivalue

See also

```
qpp::QEngine(QCircuit&&)
```

Note

The initial underlying quantum state is set to $|0\rangle^{\otimes n}$

Parameters

```
qc Quantum circuit
```

Default copy constructor.

Disables rvalue QCircuit.

```
7.58.2.4 ~QEngine()
```

```
virtual qpp::QEngine::~QEngine ( ) [virtual], [default]
```

Default virtual destructor.

7.58.3 Member Function Documentation

```
7.58.3.1 display()
```

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the state of the engine

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

Executes one step in the quantum circuit.

Parameters

```
elem Step to be executed
```

Reimplemented in qpp::QNoisyEngine < NoiseModel >.

Executes one step in the quantum circuit.

Parameters

```
it Iterator to the step to be executed
```

```
7.58.3.4 execute() [3/3]

void qpp::QEngine::execute (
        idx reps = 1,
        bool clear_stats = true ) [inline]
```

Executes the entire quantum circuit.

Parameters

reps	Number of repetitions
clear_stats	Resets the collected measurement statistics hash table before the run

```
7.58.3.5 get_circuit()
```

```
const QCircuit& qpp::QEngine::get_circuit ( ) const [inline], [noexcept]
```

Quantum circuit.

Returns

Underlying quantum circuit

```
7.58.3.6 get_dit()
```

```
idx qpp::QEngine::get_dit (
        idx i ) const [inline]
```

Value of the classical dit at position i.

Parameters

```
i Classical dit index
```

Returns

Value of the classical dit at position i

```
7.58.3.7 get_dits()
```

```
std::vector<idx> qpp::QEngine::get_dits ( ) const [inline]
```

Vector with the values of the underlying classical dits.

Returns

Vector of underlying classical dits

```
7.58.3.8 get_measured() [1/2]
```

```
bool qpp::QEngine::get_measured (
          idx i ) const [inline]
```

Check whether qudit \emph{i} was already measured.

Parameters

i Qudit index

Returns

True if qudit i was already measured, false othwewise

```
7.58.3.9 get_measured() [2/2]
std::vector<idx> qpp::QEngine::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

7.58.3.10 get_non_measured()

```
std::vector<idx> qpp::QEngine::get_non_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

Returns

Vector of non-measured qudit indexes

```
7.58.3.11 get_probs()
```

```
std::vector<double> qpp::QEngine::get_probs ( ) const [inline]
```

Vector of underlying measurement outcome probabilities.

Those should be interpreted as conditional probabilities based on the temporal order of the measurements, i.e. if we measure qubit 0, then measure qubit 1, and finally qubit 2, the resulting vector of outcome probabilities probs[2] should be interpreted as the conditional probability of qubit 2 having the outcome it had given that qubit 1 and qubit 0 had their given outcomes, respectively. As an example, if we measure the qubit 0 followed by the qubit 1 of a maximally entangled state $(|00\rangle + |11\rangle)/\sqrt{2}$, then the vector of outcome probabilities will be [0.5, 1].

Note

The probability vector has the same length as the vector of classical dits. If the measurement result is stored at the index c_reg , then the outcome probability is automatically stored at the same index c_reg in the probability vector.

Returns

Vector of underlying measurement outcome probabilities

7.58.3.12 get_psi()

```
ket qpp::QEngine::get_psi ( ) const [inline]
```

Underlying quantum state.

Returns

Underlying quantum state

7.58.3.13 get_relative_pos_()

```
\label{eq:condition} $$ std::vector < idx> qpp::QEngine::get_relative_pos_ ($$ std::vector < idx>v ) [inline], [protected]
```

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

Parameters



Returns

Vector of qudit indexes

7.58.3.14 get_stats()

```
const std::map<std::string, idx, internal::EqualSameSizeStringDits>& qpp::QEngine::get_stats (
) const [inline]
```

Measurement statistics for multiple runs.

Returns

Hash table with collected measurement statistics for multiple runs, with hash key being the string representation of the vector of measurement results and value being the number of occurrences (of the vector of measurement results), with the most significant bit located at index 0 (i.e. top/left).

7.58.3.15 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

7.58.3.16 reset()

```
void qpp::QEngine::reset ( ) [inline]
```

Resets the engine.

Re-initializes everything to zero and sets the initial state to $|0\rangle^{\otimes n}$

7.58.3.17 reset_stats()

```
QEngine& qpp::QEngine::reset_stats ( ) [inline]
```

Resets the collected measurement statistics hash table.

Returns

Reference to the current instance

7.58.3.18 set_dit()

Sets the classical dit at position i.

Parameters

i	Classical dit index
value	Classical dit value

Returns

Reference to the current instance

7.58.3.19 set_measured_()

```
void qpp::QEngine::set_measured_ (
          idx i ) [inline], [protected]
```

Marks qudit *i* as measured then re-label accordingly the remaining non-measured qudits.

Parameters

i Qudit index

7.58.3.20 set_psi()

```
QEngine& qpp::QEngine::set_psi (
                      const ket & psi ) [inline]
```

Sets the underlying quantum state to psi.

Note

The order is lexicographical with respect to the remaining non-measured qudits

Parameters

```
psi State vector
```

Returns

Reference to the current instance

7.58.3.21 to_JSON()

```
std::string qpp::QEngine::to_JSON (
          bool enclosed_in_curly_brackets = true ) const [inline], [override], [virtual]
```

qpp::IJSON::to_JSON() override

Displays the state of the engine in JSON format

Parameters

enclosed_in_curly_brackets	If true, encloses the result in curly brackets
----------------------------	--

Returns

String containing the JSON representation of the state of the engine

Implements qpp::IJSON.

7.58.4 Member Data Documentation

```
7.58.4.1 qc_
const QCircuit* qpp::QEngine::qc_ [protected]
pointer to constant quantum circuit

7.58.4.2 st_
struct qpp::QEngine::state_ qpp::QEngine::st_ [protected]
current state of the engine
```

7.58.4.3 stats_

```
std::map<std::string, idx, internal::EqualSameSizeStringDits> qpp::QEngine::stats_ [protected]
```

measurement statistics for multiple runs

The documentation for this class was generated from the following file:


· classes/circuits/engines.h

7.59 qpp::QNoisyEngine < NoiseModel > Class Template Reference


Noisy quantum circuit engine, executes qpp::QCircuit.

```
#include <classes/circuits/engines.h>
```

 $Inheritance\ diagram\ for\ qpp:: QNoisyEngine < NoiseModel >:$



Collaboration diagram for qpp::QNoisyEngine < NoiseModel >:



Public Member Functions

QNoisyEngine (const QCircuit &qc, const NoiseModel &noise)

Constructs a noisy quantum engine out of a quantum circuit.

- void execute (const QCircuit::iterator::value_type &elem) override Executes one step in the quantum circuit.
- std::vector < std::vector < idx > > get_noise_results () const
 Vector of noise results obtained before every step in the circuit.
- virtual void execute (const QCircuit::iterator::value type &elem)

Executes one step in the quantum circuit.

- void execute (const QCircuit::iterator &it)
 - Executes one step in the quantum circuit.
- void execute (idx reps=1, bool clear_stats=true)

Executes the entire quantum circuit.

Private Attributes

NoiseModel noise_

quantum noise model

 $\bullet \ \, \text{std::vector} < \text{std::vector} < \text{idx} >> \text{noise_results_} \\$

noise results

Additional Inherited Members

7.59.1 Detailed Description

template<typename NoiseModel> class qpp::QNoisyEngine< NoiseModel >

Noisy quantum circuit engine, executes qpp::QCircuit.

See also

qpp::QEngine, qpp::QCircuit, qpp::NoiseBase

Assumes an uncorrelated noise model that is applied to each non-measured qubit before every non-measurement step in the logical circuit. To add noise before a measurement, insert a no-op via qpp::QCircuit::nop().

Template Parameters

NoiseModel	Quantum noise model, should be derived from qpp::NoiseBase
------------	--

7.59.2 Constructor & Destructor Documentation

7.59.2.1 QNoisyEngine()

Constructs a noisy quantum engine out of a quantum circuit.

Parameters

qc	Quantum circuit
noise	Quantum noise model

7.59.3 Member Function Documentation

```
7.59.3.1 execute() [1/4]

template<typename NoiseModel >
virtual void qpp::QEngine::execute [inline]
```

Executes one step in the quantum circuit.

Parameters

elem	Step to be executed

```
7.59.3.2 execute() [2/4]
```

```
template<typename NoiseModel >
void qpp::QEngine::execute [inline]
```

Executes the entire quantum circuit.

Parameters

reps	Number of repetitions
clear_stats	Resets the collected measurement statistics hash table before the run

7.59.3.3 execute() [3/4]

```
template<typename NoiseModel >
void qpp::QEngine::execute [inline]
```

Executes one step in the quantum circuit.

Parameters

```
it Iterator to the step to be executed
```

7.59.3.4 execute() [4/4]

Executes one step in the quantum circuit.

Parameters

```
elem Step to be executed
```

Reimplemented from qpp::QEngine.

7.59.3.5 get_noise_results()

```
template<typename NoiseModel >
std::vector<std::vector<idx> > qpp::QNoisyEngine< NoiseModel >::get_noise_results ( ) const
[inline]
```

Vector of noise results obtained before every step in the circuit.

The first vector contains the noise measurement results obtained before applying the first step in the circuit, and so on, ordered by non-measured qudits. That is, the first element in the vector corresponding to noise obtained before a given step in the circuit represents the noise result obtained on the first non-measured qudit etc.

Returns

Vector of noise results

7.59.4 Member Data Documentation

```
7.59.4.1 noise_
```

```
template<typename NoiseModel >
NoiseModel qpp::QNoisyEngine< NoiseModel >::noise_ [private]
```

quantum noise model

7.59.4.2 noise_results_

```
template<typename NoiseModel >
std::vector<std::vector<idx> > qpp::QNoisyEngine< NoiseModel >::noise_results_ [private]
```

noise results

The documentation for this class was generated from the following file:


• classes/circuits/engines.h

7.60 qpp::QubitAmplitudeDampingNoise Class Reference


Qubit amplitude damping noise, as described in Nielsen and Chuang.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitAmplitudeDampingNoise:



Collaboration diagram for qpp::QubitAmplitudeDampingNoise:



Public Member Functions

QubitAmplitudeDampingNoise (double gamma)
 Qubit amplitude damping noise constructor.

Additional Inherited Members

7.60.1 Detailed Description

Qubit amplitude damping noise, as described in Nielsen and Chuang.

7.60.2 Constructor & Destructor Documentation

7.60.2.1 QubitAmplitudeDampingNoise()

Qubit amplitude damping noise constructor.

Parameters

gamma	Amplitude damping coefficient

The documentation for this class was generated from the following file:


· classes/noise.h

7.61 qpp::QubitBitFlipNoise Class Reference


Qubit bit flip noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitBitFlipNoise:



Collaboration diagram for qpp::QubitBitFlipNoise:



Public Member Functions

QubitBitFlipNoise (double p)
 Qubit bit flip noise constructor.

Additional Inherited Members

7.61.1 Detailed Description

Qubit bit flip noise.

7.61.2 Constructor & Destructor Documentation

7.61.2.1 QubitBitFlipNoise()

Qubit bit flip noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.62 qpp::QubitBitPhaseFlipNoise Class Reference


Qubit bit-phase flip (dephasing) noise.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitBitPhaseFlipNoise:



Collaboration diagram for qpp::QubitBitPhaseFlipNoise:



Public Member Functions

QubitBitPhaseFlipNoise (double p)
 Qubit bit-phase flip noise constructor.

Additional Inherited Members

7.62.1 Detailed Description

Qubit bit-phase flip (dephasing) noise.

7.62.2 Constructor & Destructor Documentation

7.62.2.1 QubitBitPhaseFlipNoise()

Qubit bit-phase flip noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.63 qpp::QubitDepolarizingNoise Class Reference


Qubit depolarizing noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitDepolarizingNoise:



Collaboration diagram for qpp::QubitDepolarizingNoise:



Public Member Functions

QubitDepolarizingNoise (double p)
 Qubit depolarizing noise constructor.

Additional Inherited Members

7.63.1 Detailed Description

Qubit depolarizing noise.

7.63.2 Constructor & Destructor Documentation

7.63.2.1 QubitDepolarizingNoise()

```
\label{eq:qpp::QubitDepolarizingNoise::QubitDepolarizingNoise (} \\ \text{double } p \text{ ) } \quad \text{[inline], [explicit]}
```

Qubit depolarizing noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


classes/noise.h

7.64 qpp::QubitPhaseDampingNoise Class Reference


Qubit phase damping noise, as described in Nielsen and Chuang.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitPhaseDampingNoise:



Collaboration diagram for qpp::QubitPhaseDampingNoise:



Public Member Functions

QubitPhaseDampingNoise (double lambda)
 Qubit phase damping noise constructor.

Additional Inherited Members

7.64.1 Detailed Description

Qubit phase damping noise, as described in Nielsen and Chuang.

7.64.2 Constructor & Destructor Documentation

7.64.2.1 QubitPhaseDampingNoise()

```
\label{eq:qpp::QubitPhaseDampingNoise::QubitPhaseDampingNoise (} \\ \mbox{double } lambda \mbox{ ) [inline], [explicit]}
```

Qubit phase damping noise constructor.

Parameters

lambda	Phase damping coefficient

The documentation for this class was generated from the following file:


· classes/noise.h

7.65 qpp::QubitPhaseFlipNoise Class Reference


Qubit phase flip (dephasing) noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitPhaseFlipNoise:



Collaboration diagram for qpp::QubitPhaseFlipNoise:



Public Member Functions

QubitPhaseFlipNoise (double p)
 Qubit phase flip (dephasing) noise constructor.

Additional Inherited Members

7.65.1 Detailed Description

Qubit phase flip (dephasing) noise.

7.65.2 Constructor & Destructor Documentation

7.65.2.1 QubitPhaseFlipNoise()

Qubit phase flip (dephasing) noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.66 qpp::exception::QuditAlreadyMeasured Class Reference


Qudit was already measured exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::QuditAlreadyMeasured:



Collaboration diagram for qpp::exception::QuditAlreadyMeasured:



Public Member Functions

- std::string description () const override
 - Exception description.
- Exception (const std::string &where)

Constructs an exception.

7.66.1 Detailed Description

Qudit was already measured exception.

The qudit was already measured and cannot be measured again

7.66.2 Member Function Documentation

7.66.2.1 description()

std::string qpp::exception::QuditAlreadyMeasured::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.66.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.67 qpp::QuditDepolarizingNoise Class Reference


Qudit depolarizing noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QuditDepolarizingNoise:



Collaboration diagram for qpp::QuditDepolarizingNoise:



Public Member Functions

QuditDepolarizingNoise (double p, idx d)
 Qudit depolarizing noise constructor.

Private Member Functions

• std::vector< cmat > fill_Ks_ (idx d) const

Fills the Kraus operator vector.

std::vector< double > fill_probs_ (double p, idx d) const
 Fills the probability vector.

Additional Inherited Members

7.67.1 Detailed Description

Qudit depolarizing noise.

7.67.2 Constructor & Destructor Documentation

7.67.2.1 QuditDepolarizingNoise()

```
qpp::QuditDepolarizingNoise::QuditDepolarizingNoise ( double p,  idx \ d \ ) \ \ [inline], \ [explicit]
```

Qudit depolarizing noise constructor.

Parameters

р	Noise probability
d	Qudit dimension

7.67.3 Member Function Documentation

```
7.67.3.1 fill_Ks_()
```

Fills the Kraus operator vector.

Parameters

```
d Qudit dimension
```

Returns

Vector of Kraus operators representing the depolarizing noise

```
7.67.3.2 fill_probs_()
```

Fills the probability vector.

Parameters

р	Probability
d	Qudit dimension

Returns

Probability vector

The documentation for this class was generated from the following file:


• classes/noise.h

7.68 qpp::RandomDevices Class Reference


Singleton class that manages the source of randomness in the library.

#include <classes/random_devices.h>

Inheritance diagram for qpp::RandomDevices:



Collaboration diagram for qpp::RandomDevices:



Public Member Functions

• std::mt19937 & get_prng ()

Returns a reference to the internal PRNG object.

• std::istream & load (std::istream &is)

Loads the state of the PRNG from an input stream.

• std::ostream & save (std::ostream &os) const

Saves the state of the PRNG to an output stream.

Private Member Functions

• RandomDevices ()

Initializes and seeds the random number generators.

∼RandomDevices ()=default

Default destructor.

Private Attributes

 std::random_device rd_ used to seed std::mt19937 prng_

std::mt19937 prng_

Mersenne twister random number generator.

Friends

class internal::Singleton < RandomDevices >

Additional Inherited Members

7.68.1 Detailed Description

Singleton class that manages the source of randomness in the library.

Warning

This class DOES NOT seed the standard C number generator used by Eigen::Matrix::Random(), since it is not thread safe. Do not use Eigen::Matrix::Random() or functions that depend on the C style random number engine, but use qpp::rand() instead!

7.68.2 Constructor & Destructor Documentation

7.68.2.1 RandomDevices()

```
qpp::RandomDevices::RandomDevices ( ) [inline], [private]
```

Initializes and seeds the random number generators.

7.68.2.2 ~RandomDevices()

```
\verb"qpp::RandomDevices::$\sim$RandomDevices ( ) [private], [default]
```

Default destructor.

7.68.3 Member Function Documentation

```
7.68.3.1 get_prng()
```

```
std::mt19937& qpp::RandomDevices::get_prng ( ) [inline]
```

Returns a reference to the internal PRNG object.

Returns

Reference to the internal PRNG object

7.68.3.2 load()

Loads the state of the PRNG from an input stream.

Parameters

```
is Input stream
```

Returns

Input stream

7.68.3.3 save()

Saves the state of the PRNG to an output stream.

Parameters

os Output stream

Returns

Output stream

7.68.4 Friends And Related Function Documentation

```
7.68.4.1 internal::Singleton < Random Devices >
```

```
friend class internal::Singleton< RandomDevices > [friend]
```

7.68.5 Member Data Documentation

```
7.68.5.1 prng_
```

```
std::mt19937 qpp::RandomDevices::prng_ [private]
```

Mersenne twister random number generator.

```
7.68.5.2 rd_
```

```
std::random_device qpp::RandomDevices::rd_ [private]
```

used to seed std::mt19937 prng_

The documentation for this class was generated from the following file:

• classes/random_devices.h

7.69 qpp::internal::Singleton < T > Class Template Reference

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

```
#include <internal/classes/singleton.h>
```

Static Public Member Functions

- static T & get_instance () noexcept(std::is_nothrow_constructible < T >::value)
- static T & get_thread_local_instance () noexcept(std::is_nothrow_constructible < T >::value)

Protected Member Functions

- Singleton () noexcept=default
- Singleton (const Singleton &)=delete
- Singleton & operator= (const Singleton &)=delete
- virtual ∼Singleton ()=default

7.69.1 Detailed Description

```
\label{template} \mbox{typename T} > \\ \mbox{class qpp::internal::Singleton} < \mbox{T} > \\
```

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

To implement a singleton, derive your class from qpp::internal::Singleton, make qpp::internal::Singleton a friend of your class, then declare the constructor and destructor of your class as private. To get an instance, use the static member function qpp::internal::Singleton::get_instance() (qpp::internal::Singleton::get_thread_local_instance()), which returns a reference (thread_local_reference) to your newly created singleton (thread-safe in C++11).

Example:

See also

Code of qpp::Codes, qpp::Gates, qpp::Init, qpp::RandomDevices, qpp::States or qpp.h for real world examples of usage.

7.69.2 Constructor & Destructor Documentation

```
7.69.2.1 Singleton() [1/2]

template<typename T>

qpp::internal::Singleton< T >::Singleton ( ) [protected], [default], [noexcept]
```

7.69.2.2 Singleton() [2/2] template<typename T> qpp::internal::Singleton< T >::Singleton (const Singleton< T > &) [protected], [delete] 7.69.2.3 \sim Singleton() template<typename T> $\label{thm:prop} \mbox{virtual qpp::internal::Singleton< $T>::\sim$Singleton () [protected], [virtual], [default]$ 7.69.3 Member Function Documentation 7.69.3.1 get_instance() template<typename T> static T& qpp::internal::Singleton< T >::get_instance () [inline], [static], [noexcept] 7.69.3.2 get_thread_local_instance() template<typename T> static T& qpp::internal::Singleton< T >::get_thread_local_instance () [inline], [static], [noexcept] 7.69.3.3 operator=() template<typename T> Singleton& qpp::internal::Singleton< T >::operator= (const Singleton< T > &) [protected], [delete]

The documentation for this class was generated from the following file:


• internal/classes/singleton.h

7.70 qpp::exception::SizeMismatch Class Reference

Size mismatch exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SizeMismatch:



Collaboration diagram for qpp::exception::SizeMismatch:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.70.1 Detailed Description

Size mismatch exception.

Sizes do not match

7.70.2 Member Function Documentation

7.70.2.1 description()

std::string qpp::exception::SizeMismatch::description () const [inline], [override], [virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.70.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

<i>where</i> Text repre	senting where the exception occurred
---------------------------	--------------------------------------

The documentation for this class was generated from the following file:


· classes/exception.h

7.71 qpp::QEngine::state_ Class Reference

Current state of the engine.

#include <classes/circuits/engines.h>

Collaboration diagram for qpp::QEngine::state_:



Public Member Functions

• state_ (const QCircuit *qc)

Constructor.

• state_ (const state_ &)=default

Default copy constructor.

• state_ & operator= (const state_ &)=default

Default copy assignment operator.

• void reset ()

Resets the engine state.

Public Attributes

```
• const QCircuit * qc_
```

ket psi_ {}

state vector

std::vector< double > probs_{{}}

measurement probabilities

std::vector< idx > dits_{{}}

classical dits

std::vector< idx > subsys_{{}}

7.71.1 Detailed Description

Current state of the engine.

7.71.2 Constructor & Destructor Documentation

Constructor.

Parameters

qc Non-owning pointer to the parent const quantum circuit

Default copy constructor.

7.71.3 Member Function Documentation

7.71.3.1 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

```
7.71.3.2 reset()
```

```
void qpp::QEngine::state_::reset ( ) [inline]
```

Resets the engine state.

7.71.4 Member Data Documentation

```
7.71.4.1 dits_
std::vector<idx> qpp::QEngine::state_::dits_ {}
classical dits
7.71.4.2 probs_
std::vector<double> qpp::QEngine::state_::probs_ {}
measurement probabilities
7.71.4.3 psi_
ket qpp::QEngine::state_::psi_ {}
state vector
7.71.4.4 qc_
const QCircuit* qpp::QEngine::state_::qc_
non-owning pointer to the parent const quantum circuit
7.71.4.5 subsys_
std::vector<idx> qpp::QEngine::state_::subsys_ {}
```

keeps track of the measured subsystems, re-label them after measurements

The documentation for this class was generated from the following file:

• classes/circuits/engines.h

7.72 qpp::NoiseType::StateDependent Class Reference

Template tag, used whenever the noise is state-dependent.

#include <classes/noise.h>

7.72.1 Detailed Description

Template tag, used whenever the noise is state-dependent.

The documentation for this class was generated from the following file:

· classes/noise.h

7.73 qpp::NoiseType::StateIndependent Class Reference

Template tag, used whenever the noise is state-independent.

#include <classes/noise.h>

7.73.1 Detailed Description

Template tag, used whenever the noise is state-independent.

The documentation for this class was generated from the following file:


classes/noise.h

7.74 qpp::States Class Reference


const Singleton class that implements most commonly used states

#include <classes/states.h>

Inheritance diagram for qpp::States:



Collaboration diagram for qpp::States:



Public Member Functions

• ket mes (idx d=2) const

Maximally entangled state of 2 qudits.

• ket zero (idx n, idx d=2) const

Zero state of n qudits.

• ket one (idx n, idx d=2) const

One state of n qudits.

• ket jn (idx j, idx n, idx d=2) const

 $|j\rangle^{\otimes n}$ state of n qudits

• ket plus (idx n) const

Plus state of n qubits.

• ket minus (idx n) const

Minus state of n qubits.

Public Attributes

```
    ket x0 {ket::Zero(2)}
```

Pauli Sigma-X 0-eigenstate |+>

ket x1 {ket::Zero(2)}

Pauli Sigma-X 1-eigenstate |->

ket y0 {ket::Zero(2)}

Pauli Sigma-Y 0-eigenstate |y+>

ket y1 {ket::Zero(2)}

Pauli Sigma-Y 1-eigenstate |y->

ket z0 {ket::Zero(2)}

Pauli Sigma-Z 0-eigenstate | 0>

ket z1 {ket::Zero(2)}

Pauli Sigma-Z 1-eigenstate | 1>

• cmat px0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

• cmat px1 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.

```
    cmat py0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 0-eigenstate |y+\rangle < y+|.

    cmat py1 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.

    cmat pz0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
• cmat pz1 {cmat::Zero(2, 2)}
      Projector onto the Pauli Sigma-Z 1-eigenstate |1><1|.
ket b00 {ket::Zero(4)}
      Bell-00 state, as described in Nielsen and Chuang.

    ket b01 {ket::Zero(4)}

      Bell-01 state, as described in Nielsen and Chuang.

    ket b10 {ket::Zero(4)}

      Bell-10 state, as described in Nielsen and Chuang.
ket b11 {ket::Zero(4)}
      Bell-11 state, as described in Nielsen and Chuang.

    cmat pb00 {cmat::Zero(4, 4)}

      Projector onto the Bell-00 state.

    cmat pb01 {cmat::Zero(4, 4)}

      Projector onto the Bell-01 state.

    cmat pb10 {cmat::Zero(4, 4)}

      Projector onto the Bell-10 state.

    cmat pb11 {cmat::Zero(4, 4)}

      Projector onto the Bell-11 state.
ket GHZ {ket::Zero(8)}
      GHZ state.

    ket W {ket::Zero(8)}

      W state.
cmat pGHZ {cmat::Zero(8, 8)}
      Projector onto the GHZ state.
cmat pW {cmat::Zero(8, 8)}
      Projector onto the W state.
```

Private Member Functions

- States ()
- ∼States ()=default

Default destructor.

Friends

class internal::Singleton < const States >

Additional Inherited Members

7.74.1 Detailed Description

const Singleton class that implements most commonly used states

7.74.2 Constructor & Destructor Documentation

7.74.2.1 States()

```
qpp::States::States ( ) [inline], [private]
```

Initialize the states

```
7.74.2.2 ∼States()
```

```
qpp::States::~States ( ) [private], [default]
```

Default destructor.

7.74.3 Member Function Documentation

7.74.3.1 jn()

 $|j\rangle^{\otimes n}$ state of *n* qudits

Parameters

j	Non-negative integer
n	Non-negative integer
d	Subsystem dimensions

Returns

```
|j\rangle^{\otimes n} state of n qudits
```

7.74.3.2 mes()

```
ket qpp::States::mes (
idx d = 2 ) const [inline]
```

Maximally entangled state of 2 qudits.

Parameters

d Subsystem dimensions

Returns

Maximally entangled state $\frac{1}{\sqrt{d}} \sum_{j=0}^{d-1} |jj\rangle$ of 2 qudits

7.74.3.3 minus()

```
ket qpp::States::minus (
          idx n ) const [inline]
```

Minus state of n qubits.

Parameters

n Non-negative integer

Returns

Minus state $|-\rangle^{\otimes n}$ of n qubits

7.74.3.4 one()

```
ket qpp::States::one (
        idx n,
        idx d = 2 ) const [inline]
```

One state of *n* qudits.

Parameters

n	Non-negative integer
d	Subsystem dimensions

Returns

One state $|1\rangle^{\otimes n}$ of n qudits

7.74.3.5 plus()

```
ket qpp::States::plus (
         idx n ) const [inline]
```

Plus state of *n* qubits.

Parameters

```
n Non-negative integer
```

Returns

Plus state $|+\rangle^{\otimes n}$ of n qubits

7.74.3.6 zero()

```
ket qpp::States::zero (
         idx n,
         idx d = 2 ) const [inline]
```

Zero state of *n* qudits.

Parameters

n	Non-negative integer
d	Subsystem dimensions

Returns

Zero state $|0\rangle^{\otimes n}$ of n qudits

7.74.4 Friends And Related Function Documentation

```
7.74.4.1 internal::Singleton < const States >
```

```
friend class internal::Singleton< const States > [friend]
```

7.74.5 Member Data Documentation

```
7.74.5.1 b00
```

```
ket qpp::States::b00 {ket::Zero(4)}
```

Bell-00 state, as described in Nielsen and Chuang.

7.74.5.2 b01

```
ket qpp::States::b01 {ket::Zero(4)}
```

Bell-01 state, as described in Nielsen and Chuang.

7.74.5.3 b10

```
ket qpp::States::b10 {ket::Zero(4)}
```

Bell-10 state, as described in Nielsen and Chuang.

7.74.5.4 b11

```
ket qpp::States::b11 {ket::Zero(4)}
```

Bell-11 state, as described in Nielsen and Chuang.

7.74.5.5 GHZ

```
ket qpp::States::GHZ {ket::Zero(8)}
```

GHZ state.

7.74.5.6 pb00

```
cmat qpp::States::pb00 {cmat::Zero(4, 4)}
```

Projector onto the Bell-00 state.

```
7.74.5.7 pb01
cmat qpp::States::pb01 {cmat::Zero(4, 4)}
Projector onto the Bell-01 state.
7.74.5.8 pb10
cmat qpp::States::pb10 {cmat::Zero(4, 4)}
Projector onto the Bell-10 state.
7.74.5.9 pb11
cmat qpp::States::pb11 {cmat::Zero(4, 4)}
Projector onto the Bell-11 state.
7.74.5.10 pGHZ
cmat qpp::States::pGHZ {cmat::Zero(8, 8)}
Projector onto the GHZ state.
7.74.5.11 pW
cmat qpp::States::pW {cmat::Zero(8, 8)}
Projector onto the W state.
7.74.5.12 px0
```

cmat qpp::States::px0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

```
7.74.5.13 px1
cmat qpp::States::px1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.
7.74.5.14 py0
cmat qpp::States::py0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 0-eigenstate |y+>< y+|.
7.74.5.15 py1
cmat qpp::States::py1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.
7.74.5.16 pz0
cmat qpp::States::pz0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
7.74.5.17 pz1
cmat qpp::States::pz1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 1-eigenstate |1><1|.
7.74.5.18 W
ket qpp::States::W {ket::Zero(8)}
```

W state.

```
7.74.5.19 x0
ket qpp::States::x0 {ket::Zero(2)}
Pauli Sigma-X 0-eigenstate |+>
7.74.5.20 x1
ket qpp::States::x1 {ket::Zero(2)}
Pauli Sigma-X 1-eigenstate |->
7.74.5.21 y0
ket qpp::States::y0 {ket::Zero(2)}
Pauli Sigma-Y 0-eigenstate |y+>
7.74.5.22 y1
ket qpp::States::y1 {ket::Zero(2)}
Pauli Sigma-Y 1-eigenstate |y->
7.74.5.23 z0
ket qpp::States::z0 {ket::Zero(2)}
Pauli Sigma-Z 0-eigenstate |0>
7.74.5.24 z1
ket qpp::States::z1 {ket::Zero(2)}
Pauli Sigma-Z 1-eigenstate |1>
The documentation for this class was generated from the following file:
```


classes/states.h

7.75 qpp::exception::SubsysMismatchDims Class Reference


Subsystems mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SubsysMismatchDims:



Collaboration diagram for qpp::exception::SubsysMismatchDims:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.75.1 Detailed Description

Subsystems mismatch dimensions exception.

std::vector<idx> of subsystem labels has duplicates, or has entries that are larger than the size of the std← ::vector<idx> of dimensions

7.75.2 Member Function Documentation

7.75.2.1 description()

std::string qpp::exception::SubsysMismatchDims::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.75.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.76 qpp::Timer < T, CLOCK_T > Class Template Reference


Chronometer.

#include <classes/timer.h>

Inheritance diagram for qpp::Timer < T, CLOCK_T >:



Collaboration diagram for qpp::Timer < T, CLOCK_T >:



Public Member Functions

• Timer () noexcept

Constructs an instance with the current time as the starting point.

• virtual \sim Timer ()=default

Default virtual destructor.

· void tic () noexcept

Resets the chronometer.

• const Timer & toc () noexcept

Stops the chronometer.

• double tics () const noexcept

Time passed in the duration specified by T.

• template<typename U = T>

U get_duration () const noexcept

Duration specified by U.

Protected Attributes

- CLOCK_T::time_point start_
- CLOCK_T::time_point end_

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display() override*

7.76.1 Detailed Description

```
template < typename\ T = std::chrono::duration < double >, typename\ CLOCK\_T = std::chrono::steady\_clock > class\ qpp::Timer < T,\ CLOCK\_T >
```

Chronometer.

Template Parameters

T	Tics duration, default is std::chrono::duration <double>, i.e. seconds in double precision</double>
CLOCK⊷	Clock's type, default is std::chrono::steady_clock, not affected by wall clock changes during runtime
_ <i>T</i>	

7.76.2 Constructor & Destructor Documentation

7.76.2.1 Timer()

Constructs an instance with the current time as the starting point.

7.76.2.2 \sim Timer()

```
\label{lock-type-ame} $$ $$ template<type-name T = std::chrono::steady \leftarrow $$ $$ $$ clock> $$ virtual $$ qpp::Timer< T, CLOCK_T >::~Timer ( ) [virtual], [default] $$
```

Default virtual destructor.

7.76.3 Member Function Documentation

7.76.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream the number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc()

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.76.3.2 get_duration()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady 
_clock>
template<typename U = T>
U qpp::Timer< T, CLOCK_T >::get_duration ( ) const [inline], [noexcept]
```

Duration specified by U.

Template Parameters

U Duration, default is T, which defaults to std::chrono::duration<double>, i.e. seconds in double precision

Returns

Duration that passed between the instantiation/reset and invocation of qpp::Timer::toc()

7.76.3.3 tic()

```
 \begin{tabular}{ll} template < type name T = std::chrono::duration < double>, type name CLOCK_T = std::chrono::steady & clock> \\ void qpp::Timer < T, CLOCK_T >::tic ( ) [inline], [noexcept] \\ \end{tabular}
```

Resets the chronometer.

Resets the starting/ending point to the current time

7.76.3.4 tics()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
double qpp::Timer< T, CLOCK_T >::tics ( ) const [inline], [noexcept]
```

Time passed in the duration specified by T.

Returns

Number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc()

7.76.3.5 toc()

```
 \begin{tabular}{ll} template < type name $T = std::chrono::steady \leftarrow \_clock > \\ const $Timer\& $qpp::Timer < T, $CLOCK_T > ::toc ( ) [inline], [noexcept] \end{tabular}
```

Stops the chronometer.

Set the current time as the ending point

Returns

Reference to the current instance

7.76.4 Member Data Documentation

7.76.4.1 end

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::end_ [protected]
```

7.76.4.2 start_

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::start_ [protected]
```

The documentation for this class was generated from the following file:


· classes/timer.h

7.77 qpp::exception::TypeMismatch Class Reference


Type mismatch exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::TypeMismatch:



Collaboration diagram for qpp::exception::TypeMismatch:



Public Member Functions

- std::string description () const override
 - Exception description.
- Exception (const std::string &where)

Constructs an exception.

7.77.1 Detailed Description

Type mismatch exception.

Scalar types do not match

7.77.2 Member Function Documentation

7.77.2.1 description()

std::string qpp::exception::TypeMismatch::description () const [inline], [override], [virtual]
Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.77.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


• classes/exception.h

7.78 qpp::exception::UndefinedType Class Reference


Not defined for this type exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception:: Undefined Type:$



Collaboration diagram for qpp::exception::UndefinedType:



Public Member Functions

- std::string description () const override
 - Exception description.
- Exception (const std::string &where)

Constructs an exception.

7.78.1 Detailed Description

Not defined for this type exception.

Templated specialization is not defined for this type

7.78.2 Member Function Documentation

7.78.2.1 description()

std::string qpp::exception::UndefinedType::description () const [inline], [override], [virtual]
Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.78.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


• classes/exception.h

7.79 qpp::exception::Unknown Class Reference


Unknown exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Unknown:



Collaboration diagram for qpp::exception::Unknown:



Public Member Functions

- std::string description () const override
 - Exception description.
- Exception (const std::string &where)

Constructs an exception.

7.79.1 Detailed Description

Unknown exception.

Thrown when no other exception is suitable (not recommended, it is better to define another suitable exception type)

7.79.2 Member Function Documentation

7.79.2.1 description()

std::string qpp::exception::Unknown::description () const [inline], [override], [virtual]
Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.79.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--


The documentation for this class was generated from the following file:

• classes/exception.h


7.80 qpp::QCircuit::iterator::value_type_ Class Reference

Value type class for qpp::QCircuit::iterator.

Inheritance diagram for qpp::QCircuit::iterator::value_type_:



Collaboration diagram for qpp::QCircuit::iterator::value_type_:



Public Member Functions

```
    value_type_ (const QCircuit *value_type_qc)
        Constructor.
    value_type_ (const value_type_ &)=default
        Default copy constructor.
    value_type_ & operator= (const value_type_ &)=default
        Default copy assignment operator.
```

Public Attributes

```
    const QCircuit * value_type_qc_
        < non-owning pointer to the grand-parent const quantum circuit</li>
    StepType type_{StepType::NONE}
        step type
    idx ip_{static_cast<idx>(-1)}
        instruction pointer
    std::vector< GateStep >::const_iterator gates_ip_{gates instruction pointer}
    std::vector< MeasureStep >::const_iterator measurements_ip_{measurements instruction pointer}
```

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display() override*

7.80.1 Detailed Description

Value type class for qpp::QCircuit::iterator.

7.80.2 Constructor & Destructor Documentation

Parameters

value type qc	Pointer to constant quantum circuit
value_type_qc	i omiter to constant quantum circuit

Default copy constructor.

7.80.3 Member Function Documentation

7.80.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream the textual representation of the iterator de-referenced element

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.80.3.2 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

7.80.4 Member Data Documentation

```
7.80.4.1 gates_ip_
std::vector<GateStep>::const_iterator qpp::QCircuit::iterator::value_type_::gates_ip_ {}
gates instruction pointer
7.80.4.2 ip_
idx qpp::QCircuit::iterator::value_type_::ip_ {static_cast<idx>(-1)}
instruction pointer
7.80.4.3 measurements_ip_
\verb|std::vector<| \texttt{MeasureStep}>::const_iterator | qpp::QCircuit::iterator::value_type_::measurements\_{\leftarrow}| to the const_iterator | to the const_itera
measurements instruction pointer
7.80.4.4 type_
StepType qpp::QCircuit::iterator::value_type_::type_ {StepType::NONE}
step type
7.80.4.5 value_type_qc_
const QCircuit* qpp::QCircuit::iterator::value_type_::value_type_qc_
 < non-owning pointer to the grand-parent const quantum circuit
The documentation for this class was generated from the following file:
```


• classes/circuits/circuits.h

7.81 qpp::exception::ZeroSize Class Reference


Object has zero size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::ZeroSize:



Collaboration diagram for qpp::exception::ZeroSize:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.81.1 Detailed Description

Object has zero size exception.

Zero sized object, e.g. empty Eigen::Matrix or std::vector with no elements

7.81.2 Member Function Documentation

7.81.2.1 description()

std::string qpp::exception::ZeroSize::description () const [inline], [override], [virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.81.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:

· classes/exception.h


Chapter 8

File Documentation

8.1 classes/circuits/circuits.h File Reference

Qudit quantum circuits.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::QCircuit

Quantum circuit description.

• struct qpp::QCircuit::GateStep

One step consisting only of gates/operators in the circuit.

• struct qpp::QCircuit::MeasureStep

One step consisting only of measurements in the circuit.

· class qpp::QCircuit::iterator

Quantum circuit bound-checking (safe) iterator.

• class qpp::QCircuit::iterator::value_type_

Value type class for qpp::QCircuit::iterator.

Namespaces

qpp

Quantum++ main namespace.


8.1.1 Detailed Description

Qudit quantum circuits.

8.2 classes/circuits/engines.h File Reference

Qudit quantum engines.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::QEngine

Quantum circuit engine, executes qpp::QCircuit.

· class qpp::QEngine::state_

Current state of the engine.

class qpp::QNoisyEngine < NoiseModel >

Noisy quantum circuit engine, executes qpp::QCircuit.

Namespaces

• qpp

Quantum++ main namespace.


8.2.1 Detailed Description

Qudit quantum engines.

8.3 classes/codes.h File Reference

Quantum error correcting codes.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::Codes

const Singleton class that defines quantum error correcting codes

Namespaces

• qpp

Quantum++ main namespace.


8.3.1 Detailed Description

Quantum error correcting codes.

8.4 classes/exception.h File Reference

Exceptions.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::exception::Exception

Base class for generating Quantum++ custom exceptions.

· class qpp::exception::Unknown

Unknown exception.

class qpp::exception::ZeroSize

Object has zero size exception.

class gpp::exception::MatrixNotSquare

Matrix is not square exception.

· class qpp::exception::MatrixNotCvector

Matrix is not a column vector exception.

class qpp::exception::MatrixNotRvector

Matrix is not a row vector exception.

class qpp::exception::MatrixNotVector

Matrix is not a vector exception.

class qpp::exception::MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

• class qpp::exception::MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

class qpp::exception::MatrixNotSquareNorVector

Matrix is not square nor vector exception.

class qpp::exception::MatrixMismatchSubsys

Matrix mismatch subsystems exception.

· class qpp::exception::DimsInvalid

Invalid dimension(s) exception.

· class qpp::exception::DimsNotEqual

Dimensions not equal exception.

class qpp::exception::DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

class qpp::exception::DimsMismatchCvector

Dimension(s) mismatch column vector size exception.

class qpp::exception::DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

class qpp::exception::DimsMismatchVector

Dimension(s) mismatch vector size exception.

class qpp::exception::SubsysMismatchDims

Subsystems mismatch dimensions exception.

class qpp::exception::PermInvalid

Invalid permutation exception.

· class qpp::exception::PermMismatchDims

Permutation mismatch dimensions exception.

class qpp::exception::NotQubitMatrix

Matrix is not 2 x 2 exception.

· class qpp::exception::NotQubitCvector

Column vector is not 2 x 1 exception.

class qpp::exception::NotQubitRvector

Row vector is not 1 x 2 exception.

class qpp::exception::NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

class qpp::exception::NotQubitSubsys

Subsystems are not qubits exception.

· class qpp::exception::NotBipartite

Not bi-partite exception.

· class qpp::exception::NoCodeword

Codeword does not exist exception.

class qpp::exception::OutOfRange

Argument out of range exception.

class qpp::exception::TypeMismatch

Type mismatch exception.

· class qpp::exception::SizeMismatch

Size mismatch exception.

class qpp::exception::UndefinedType

Not defined for this type exception.

• class qpp::exception::QuditAlreadyMeasured

Qudit was already measured exception.

class qpp::exception::Duplicates

System (e.g. std::vector) has duplicates exception.

class qpp::exception::CustomException

Custom exception.

· class qpp::exception::NotImplemented

Code not yet implemented.

· class qpp::exception::InvalidIterator

Invalid iterator.

Namespaces

• qpp

Quantum++ main namespace.

• qpp::exception

Quantum++ exception hierarchy namespace.


8.4.1 Detailed Description

Exceptions.

8.5 classes/gates.h File Reference

Quantum gates.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::Gates

const Singleton class that implements most commonly used gates

Namespaces

• qpp

Quantum++ main namespace.

8.5.1 Detailed Description

Quantum gates.

8.6 classes/idisplay.h File Reference

Display interface via the non-virtual interface (NVI) and very basic JSON serialization support interface.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

· class qpp::IJSON

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

Namespaces

• qpp

Quantum++ main namespace.


8.6.1 Detailed Description

Display interface via the non-virtual interface (NVI) and very basic JSON serialization support interface.

8.7 classes/init.h File Reference

Initialization.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::Init

const Singleton class that performs additional initializations/cleanups

Namespaces

• qpp

Quantum++ main namespace.


8.7.1 Detailed Description

Initialization.

8.8 classes/layouts.h File Reference

Various physical qudit layouts, all must implement the interface ILayout.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::ILayout

Mandatory interface for layouts.

· class qpp::Lattice

N-dimensional orthogonal lattice coordinate system.

Namespaces

qpp

Quantum++ main namespace.

8.8.1 Detailed Description

Various physical qudit layouts, all must implement the interface ILayout.


See also

qpp::ILayout

8.9 classes/noise.h File Reference

Noise models.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::NoiseType

Contains template tags used to specify the noise type.

class qpp::NoiseBase< T >

Base class for all noise models, derive your particular noise model.

• class qpp::QubitDepolarizingNoise

Qubit depolarizing noise.

• class qpp::QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

· class qpp::QubitBitFlipNoise

Qubit bit flip noise.

• class qpp::QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

• class qpp::QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

• class qpp::QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

· class qpp::QuditDepolarizingNoise

Qudit depolarizing noise.

Namespaces

• qpp

Quantum++ main namespace.


8.9.1 Detailed Description

Noise models.

8.10 classes/random_devices.h File Reference

Random devices.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::RandomDevices

Singleton class that manages the source of randomness in the library.

Namespaces

• qpp

Quantum++ main namespace.


8.10.1 Detailed Description

Random devices.

8.11 classes/reversible.h File Reference

Support for classical reversible circuits.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::Dynamic_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime.

class qpp::Bit_circuit

Classical reversible circuit simulator.

Namespaces

• qpp

Quantum++ main namespace.


8.11.1 Detailed Description

Support for classical reversible circuits.

8.12 classes/states.h File Reference

Quantum states.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::States

const Singleton class that implements most commonly used states

Namespaces

• qpp

Quantum++ main namespace.

8.12.1 Detailed Description

Quantum states.

8.13 classes/timer.h File Reference

Timing.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::Timer < T, CLOCK_T >
 Chronometer.

Namespaces

• qpp

Quantum++ main namespace.


8.13.1 Detailed Description

Timing.

8.14 constants.h File Reference

Constants.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

· qpp::literals

Enumerations

enum { qpp::RES, qpp::PROB, qpp::ST }
 Constants to be used by std::get<> on the result of qpp::measure(), qpp_measure_seq() etc.

Functions

- constexpr cplx qpp::literals::operator""_i (unsigned long long int x) noexcept User-defined literal for complex $i=\sqrt{-1}$ (integer overload)
- constexpr cplx qpp::literals::operator""_i (long double x) noexcept

User-defined literal for complex $i = \sqrt{-1}$ (real overload)

 $\bullet \ \ constexpr \ std::complex < float > qpp::literals::operator""_if \ (unsigned \ long \ long \ int \ x) \ noexcept$

User-defined literal for complex $i=\sqrt{-1}$ (integer overload)

 $\bullet \ \ constexpr \ std::complex< float > qpp::literals::operator""_if \ (long \ double \ x) \ noexcept$

User-defined literal for complex $i=\sqrt{-1}$ (real overload)

• cplx qpp::omega (idx D)

D-th root of unity.

Variables

• constexpr double qpp::chop = 1e-16

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

• constexpr idx qpp::maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

• constexpr double qpp::pi = 3.141592653589793238462643383279502884

 π

• constexpr double qpp::ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

• constexpr double qpp::infty = std::numeric_limits<double>::max()

Used to denote infinity in double precision.


8.14.1 Detailed Description

Constants.

8.15 entanglement.h File Reference

Entanglement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

```
    template<typename Derived >

  dyn col vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector<
  idx > &dims)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  dyn_col_vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  cmat qpp::schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat qpp::schmidtA (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Bob side.

    template<typename Derived >

  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Bob side.
• template<typename Derived >
  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx
  > &dims)
      Schmidt probabilities of the bi-partite pure state A.

    template<typename Derived >

  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt probabilities of the bi-partite pure state A.
• template<typename Derived >
  double qpp::entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Entanglement of the bi-partite pure state A.
• template<typename Derived >
  double <a href="mailto:qpp::entanglement">qpp::entanglement</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Entanglement of the bi-partite pure state A.

    template<typename Derived >

  double <a href="mailto:qpp::gconcurrence">qpp::gconcurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      G-concurrence of the bi-partite pure state A.

    template<typename Derived >

  double qpp::negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double <a href="mailto:qpp::negativity">qpp::negativity</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double <a href="mailto:qpp::concurrence">qpp::concurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.
```


8.15.1 Detailed Description

Entanglement functions.

8.16 entropies.h File Reference

Entropy functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

```
    template < typename Derived >
        double qpp::entropy (const Eigen::MatrixBase < Derived > &A)
```

von-Neumann entropy of the density matrix A

double qpp::entropy (const std::vector< double > &prob)

Shannon entropy of the probability distribution prob.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

double qpp::renyi (const Eigen::MatrixBase< Derived > &A, double alpha)

Renyi- α entropy of the density matrix A, for $\alpha \geq 0$.

double qpp::renyi (const std::vector< double > &prob, double alpha)

Renyi- α entropy of the probability distribution prob, for $\alpha \geq 0$.

template<typename Derived >

double qpp::tsallis (const Eigen::MatrixBase< Derived > &A, double q)

Tsallis- q entropy of the density matrix A, for $q \geq 0$.

double qpp::tsallis (const std::vector< double > &prob, double q)

Tsallis- q entropy of the probability distribution prob, for $q \geq 0$.

• template<typename Derived >

double qpp::qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const std::vector< idx > &subsysB, const std::vector< idx > &dims)

Quantum mutual information between 2 subsystems of a composite system.

• template<typename Derived >

 $\label{lem:double qpp::qmutualinfo} $$ double qpp::qmutualinfo (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &subsysA, const std::vector < idx > &subsysB, idx d=2) \\$

Quantum mutual information between 2 subsystems of a composite system.

8.16.1 Detailed Description

Entropy functions.

8.17 experimental/experimental.h File Reference

Experimental/test functions/classes.

Namespaces

• qpp

Quantum++ main namespace.

• qpp::experimental

Experimental/test functions/classes, do not use or modify.


8.17.1 Detailed Description

Experimental/test functions/classes.

8.18 functions.h File Reference

Generic quantum computing functions.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::internal::HashEigen

Functor for hashing Eigen expressions.

• class qpp::internal::EqualEigen

Functor for comparing Eigen expressions for equality.

• class qpp::internal::EqualSameSizeStringDits

Functor for comparing strings of numbers of equal sizes in lexicographical order. Establishes a strict weak ordering relation.

Namespaces

qpp

Quantum++ main namespace.

- · qpp::literals
- qpp::internal

Eigenvectors.

Internal utility functions, do not use them directly or modify them.

Functions

```
    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::transpose (const Eigen::MatrixBase< Derived > &A)
      Transpose.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::adjoint (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::inverse (const Eigen::MatrixBase< Derived > &A)
      Inverse.

    template<typename Derived >

  Derived::Scalar qpp::trace (const Eigen::MatrixBase< Derived > &A)
      Trace.

    template<typename Derived >

  Derived::Scalar qpp::det (const Eigen::MatrixBase< Derived > &A)
      Determinant.

    template<typename Derived >

  Derived::Scalar <a href="mailto:qpp::logdet">qpp::logdet</a> (const Eigen::MatrixBase</a> Derived > &A)
      Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar <a href="mailto:qpp::sum">qpp::sum</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise sum of A.
• template<typename Derived >
  Derived::Scalar <a href="mailto:open:prod">open:prod</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise product of A.

    template<typename Derived >

  double <a href="mailto:qpp::norm">qpp::norm</a> (const Eigen::MatrixBase< Derived > &A)
      Frobenius norm.

    template < typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::normalize (const Eigen::MatrixBase< Derived > &A)
      Normalizes state vector (column or row vector) or density matrix.
• template<typename Derived >
  std::pair< dyn_col_vect< cplx >, cmat > qpp::eig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition.
ullet template<typename Derived >
  dyn_col_vect< cplx > qpp::evals (const Eigen::MatrixBase< Derived > &A)
      Eigenvalues.

    template<typename Derived >

  cmat qpp::evects (const Eigen::MatrixBase< Derived > &A)
```

```
• template<typename Derived >
  std::pair< dyn_col_vect< double >, cmat > qpp::heig (const Eigen::MatrixBase< Derived > &A)
     Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > qpp::hevals (const Eigen::MatrixBase< Derived > &A)
     Hermitian eigenvalues.
• template<typename Derived >
  cmat qpp::hevects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors of Hermitian matrix.
• template<typename Derived >
  std::tuple< cmat, dyn col vect< double >, cmat > qpp::svd (const Eigen::MatrixBase< Derived > &A)
     Full singular value decomposition.
• template<typename Derived >
  dyn_col_vect< double > qpp::svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.

    template<typename Derived >

  cmat qpp::svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.

    template<typename Derived >

  cmat qpp::svdV (const Eigen::MatrixBase< Derived > &A)
     Right singular vectors.

    template<typename Derived >

  cmat qpp::funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)
• template<typename Derived >
  cmat qpp::sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.
• template<typename Derived >
  cmat qpp::absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.

    template<typename Derived >

  cmat qpp::expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.
• template<typename Derived >
  cmat qpp::logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.
• template<typename Derived >
  cmat qpp::sinm (const Eigen::MatrixBase< Derived > &A)
template<typename Derived >
  cmat qpp::cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.

    template<typename Derived >

  cmat qpp::spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::powm (const Eigen::MatrixBase< Derived > &A, idx n)
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.
template<typename Derived >
  double qpp::schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > qpp::cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const
  typename Derived::Scalar &))
```

```
Functor.
• template<typename T >
  dyn_mat< typename T::Scalar > qpp::kron (const T &head)
     Kronecker product.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > qpp::kron (const T &head, const Args &... tail)
     Kronecker product.
• template<typename Derived >
  dyn mat< typename Derived::Scalar > qpp::kron (const std::vector< Derived > &As)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::kron (const std::initializer_list< Derived > &As)
     Kronecker product.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Kronecker power.
template<typename T >
  dyn_mat< typename T::Scalar > qpp::dirsum (const T &head)
     Direct sum.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > qpp::dirsum (const T &head, const Args &... tail)
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::vector< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::initializer_list< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::reshape (const Eigen::MatrixBase< Derived > &A, idx rows,
  idx cols)
     Reshape.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > qpp::comm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Commutator.

    template<typename Derived1 , typename Derived2 >

  dyn mat< typename Derived1::Scalar > qpp::anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.
ullet template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::prj (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::grams (const std::vector< Derived > &As)
     Gram-Schmidt orthogonalization.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::grams (const std::initializer_list< Derived > &As)
     Gram-Schmidt orthogonalization.
```

dyn_mat< typename Derived::Scalar > qpp::grams (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

Gram-Schmidt orthogonalization.

std::vector< idx > qpp::n2multiidx (idx n, const std::vector< idx > &dims)

Non-negative integer index to multi-index.

idx qpp::multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

Multi-index to non-negative integer index.

ket qpp::mket (const std::vector< idx > &mask, const std::vector< idx > &dims)

Multi-partite qudit ket.

ket qpp::mket (const std::vector< idx > &mask, idx d=2)

Multi-partite qudit ket.

cmat qpp::mprj (const std::vector < idx > &mask, const std::vector < idx > &dims)

Projector onto multi-partite qudit ket.

cmat qpp::mprj (const std::vector< idx > &mask, idx d=2)

Projector onto multi-partite qudit ket.

• template<typename InputIterator >

std::vector< double > qpp::abssq (InputIterator first, InputIterator last)

Computes the absolute values squared of an STL-like range of complex numbers.

• template<typename Container >

std::vector< double > qpp::abssq (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Computes the absolute values squared of an STL-like container.

template<typename Derived >

```
std::vector< double > qpp::abssq (const Eigen::MatrixBase< Derived > &A)
```

Computes the absolute values squared of an Eigen expression.

template<typename InputIterator >

std::iterator_traits< InputIterator >::value_type qpp::sum (InputIterator first, InputIterator last)

Element-wise sum of an STL-like range.

template<typename Container >

Container::value_type qpp::sum (const Container &c, typename std::enable_if< is_iterable< Container >--:value >::type *=nullptr)

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

std::iterator traits< InputIterator >::value type qpp::prod (InputIterator first, InputIterator last)

Element-wise product of an STL-like range.

• template<typename Container >

Container::value_type qpp::prod (const Container &c, typename std::enable_if < is_iterable < Container > \leftarrow ::value >::type *=nullptr)

Element-wise product of the elements of an STL-like container.

• template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > qpp::rho2pure (const Eigen::MatrixBase< Derived > &A)
```

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

std::vector< idx > qpp::complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

template<typename Derived >

```
std::vector< double > qpp::rho2bloch (const Eigen::MatrixBase< Derived > &A)
```

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat qpp::bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

template<char... Bits>

```
ket qpp::literals::operator""_ket ()
```

Multi-partite qubit ket user-defined literal.

template<char... Bits>

bra qpp::literals::operator""_bra ()

Multi-partite qubit bra user-defined literal.

template<char... Bits>
 cmat qpp::literals::operator""_prj ()

Multi-partite qubit projector user-defined literal.

template < class T >
 void qpp::internal::hash_combine (std::size_t &seed, const T &v)
 Hash combine.

template<typename Derived >

 $std::size_t \; qpp::hash_eigen \; (const \; Eigen::MatrixBase < \; Derived > \&A, \; std::size_t \; seed=0)$

Computes the hash of en Eigen matrix/vector/expression.


8.18.1 Detailed Description

Generic quantum computing functions.

8.19 input_output.h File Reference

Input/output functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

- template<typename Derived >
 internal::IOManipEigen qpp::disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
 Eigen expression ostream manipulator.
- internal::IOManipEigen qpp::disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

template<typename InputIterator >
 internal::IOManipRange< InputIterator > qpp::disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)

Range ostream manipulator.

template<typename Container>
 internal::IOManipRange< typename Container::const_iterator > qpp::disp (const Container &c, const std
 ::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop, typename
 std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

template<typename PointerType >
 internal::IOManipPointer< PointerType > qpp::disp (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)

C-style pointer ostream manipulator.

template<typename Derived > void qpp::save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.


8.19.1 Detailed Description

Input/output functions.

8.20 instruments.h File Reference

Measurement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

ullet template<typename Derived >

 $\label{lem:dyn_col_vect} $$ dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims) $$$

Generalized inner product.

• template<typename Derived >

dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > qpp::measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template<typename Derived >
 std::tuple< std::vector< idx >, double, cmat > qpp::measure_seq (const Eigen::MatrixBase< Derived > &A,
 std::vector< idx > target, idx d=2)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.


8.20.1 Detailed Description

Measurement functions.

8.21 internal/classes/iomanip.h File Reference

Input/output manipulators.

This graph shows which files directly or indirectly include this file:



Classes

- class qpp::internal::IOManipRange
 InputIterator >
- class qpp::internal::IOManipPointer
 PointerType >
- class qpp::internal::IOManipEigen

Namespaces

dbb

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


8.21.1 Detailed Description

Input/output manipulators.

8.22 internal/classes/singleton.h File Reference

Singleton pattern via CRTP.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::internal::Singleton < T >
 Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Namespaces

qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


8.22.1 Detailed Description

Singleton pattern via CRTP.

8.23 internal/util.h File Reference

Internal utility functions.

This graph shows which files directly or indirectly include this file:



Classes

struct qpp::internal::Display_Impl_

Namespaces

• qpp

Quantum++ main namespace.

qpp::internal

Internal utility functions, do not use them directly or modify them.

Functions

- void qpp::internal::n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx qpp::internal::multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- template<typename Derived >
 bool qpp::internal::check_square_mat (const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
 bool qpp::internal::check_vector (const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
 bool qpp::internal::check_rvector (const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
 bool qpp::internal::check_cvector (const Eigen::MatrixBase< Derived > &A)
- template<typename T >
 bool qpp::internal::check_nonzero_size (const T &x) noexcept
- template<typename T1, typename T2 >
 bool qpp::internal::check_matching_sizes (const T1 &lhs, const T2 &rhs) noexcept
- bool qpp::internal::check_dims (const std::vector< idx > &dims)
- template<typename Derived >
 bool qpp::internal::check_dims_match_mat (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
 bool qpp::internal::check_dims_match_cvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- template<typename Derived >
 bool qpp::internal::check_dims_match_rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)
- bool qpp::internal::check_eq_dims (const std::vector< idx > &dims, idx dim) noexcept
- bool gpp::internal::check no duplicates (std::vector < idx > v)
- bool qpp::internal::check_subsys_match_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)
- template<typename Derived >
 bool qpp::internal::check_qubit_matrix (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
 bool qpp::internal::check_qubit_cvector (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
 bool qpp::internal::check_qubit_rvector (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
 bool qpp::internal::check_qubit_vector (const Eigen::MatrixBase< Derived > &A) noexcept
- bool qpp::internal::check_perm (const std::vector< idx > &perm)
- template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::internal::kron2 (const Eigen::MatrixBase< Derived1 > &A,
 const Eigen::MatrixBase< Derived2 > &B)
- template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::internal::dirsum2 (const Eigen::MatrixBase< Derived1 > &A,
 const Eigen::MatrixBase< Derived2 > &B)
- template<typename T >
 void qpp::internal::variadic_vector_emplace (std::vector< T > &)
- template<typename T, typename First, typename... Args>
 void qpp::internal::variadic_vector_emplace (std::vector< T > &v, First &&first, Args &&... args)
- idx qpp::internal::get_num_subsys (idx D, idx d)
- idx qpp::internal::get_dim_subsys (idx sz, idx N)
- template<typename T, typename std::enable_if< std::numeric_limits< T >::is_iec559||is_complex< T >::value >::type * = nullptr> T qpp::internal::abs chop (const T &x, double chop=qpp::chop)
- template<typename T, typename std::enable_if<!(std::numeric_limits< T >::is_iec559||is_complex< T >::value)>::type * = nullptr>
 T qpp::internal::abs_chop (const T &x, double QPP_UNUSED_chop=qpp::chop)

8.23.1 Detailed Description

Internal utility functions.

8.24 MATLAB/matlab.h File Reference

Input/output interfacing with MATLAB.

```
#include "mat.h"
#include "mex.h"
```

Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< cplx > ::type
 qpp::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::

Scalar > >::type qpp::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.


8.24.1 Detailed Description

Input/output interfacing with MATLAB.

8.25 number theory.h File Reference

Number theory functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

std::vector< int > qpp::x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double qpp::contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

• bigint qpp::gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint qpp::gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint qpp::lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint qpp::lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > qpp::invperm (const std::vector< idx > &perm)

Inverse permutation.

 $\bullet \; \mathsf{std} :: \mathsf{vector} < \mathsf{idx} > \mathsf{qpp} :: \mathsf{compperm} \; (\mathsf{const} \; \mathsf{std} :: \mathsf{vector} < \mathsf{idx} > \& \mathsf{perm}, \; \mathsf{const} \; \mathsf{std} :: \mathsf{vector} < \mathsf{idx} > \& \mathsf{sigma}) \\$

Compose permutations.

• std::vector< bigint > qpp::factors (bigint a)

Prime factor decomposition.

• bigint qpp::modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

• bigint qpp::modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple < bigint, bigint, bigint > qpp::egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint qpp::modinv (bigint a, bigint p)

Modular inverse of a mod p.

• bool qpp::isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

• bigint qpp::randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

• std::vector< std::pair< int, int > > qpp::convergents (const std::vector< int > &cf)

Convergents.

• std::vector< std::pair< int, int > > qpp::convergents (double x, idx N)

Convergents.


8.25.1 Detailed Description

Number theory functions.

8.26 operations.h File Reference

Quantum operation functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 const std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 idx d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const
 Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const
 Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

 $\bullet \ \ \mathsf{template}{<}\mathsf{typename} \ \mathsf{Derived}>$

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std \leftrightarrow ::vector< idx > &target, const std::vector< idx > &dims)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

• template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std ::vector< idx > &target, idx d=2)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat qpp::kraus2super (const std::vector< cmat > &Ks)

Superoperator matrix.

cmat qpp::kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector< cmat > qpp::choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

• cmat qpp::choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat qpp::super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace2 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

Partial trace.

template<typename Derived >

 $\label{lem:dyn_mat} $$ dyn_mat< typename\ Derived::Scalar > qpp::ptrace\ (const\ Eigen::MatrixBase<\ Derived > \&A,\ const\ std \mapsto ::vector < idx > \&target,\ idx\ d=2)$$

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Partial transpose.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2)

Partial transpose.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &perm, const std::vector< idx > &dims)

Subsystem permutation.

template<typename Derived >

 $dyn_mat < typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &perm, idx d=2)$

Subsystem permutation.

template<typename Derived >
 dyn_mat< typename Derived::Scalar > qpp::applyQFT (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

```
dyn_mat< typename Derived::Scalar > qpp::applyTFQ (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)
```

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > qpp::TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)
```

Inverse (adjoint) qudit quantum Fourier transform.

template<typename Derived >

```
\label{local_vect} $$ dyn\_col\_vect< typename \ Derived::Scalar > qpp::QFT \ (const \ Eigen::MatrixBase< \ Derived > \&A, \ idx \ d=2, \ bool \ swap=true) $$
```

Qudit quantum Fourier transform.

8.26.1 Detailed Description

Quantum operation functions.

8.27 qpp.h File Reference

Quantum++ main header file, includes all other necessary headers.

```
#include <algorithm>
#include <cassert>
#include <chrono>
#include <cmath>
#include <complex>
#include <cstdlib>
#include <cstring>
#include <exception>
#include <fstream>
#include <functional>
#include <initializer_list>
#include <iomanip>
#include <iterator>
#include <limits>
#include <map>
#include <memory>
#include <numeric>
#include <ostream>
#include <random>
#include <sstream>
#include <stdexcept>
#include <string>
#include <tuple>
#include <type_traits>
#include <unordered_map>
#include <utility>
#include <vector>
```

```
#include <Eigen/Dense>
#include <Eigen/SVD>
#include "types.h"
#include "classes/exception.h"
#include "constants.h"
#include "traits.h"
#include "classes/idisplay.h"
#include "internal/util.h"
#include "internal/classes/iomanip.h"
#include "input_output.h"
#include "internal/classes/singleton.h"
#include "classes/random_devices.h"
#include "random.h"
#include "number_theory.h"
#include "functions.h"
#include "classes/init.h"
#include "classes/codes.h"
#include "classes/gates.h"
#include "classes/states.h"
#include "statistics.h"
#include "operations.h"
#include "entropies.h"
#include "entanglement.h"
#include "instruments.h"
#include "classes/layouts.h"
#include "classes/noise.h"
#include "classes/reversible.h"
#include "classes/timer.h"
#include "classes/circuits/circuits.h"
#include "classes/circuits/engines.h"
```

Namespaces

• qpp

Quantum++ main namespace.

Macros

• #define QPP_UNUSED_

8.27.1 Detailed Description

Quantum++ main header file, includes all other necessary headers.

8.27.2 Macro Definition Documentation


8.27.2.1 QPP_UNUSED_

#define QPP_UNUSED_

8.28 random.h File Reference

Randomness-related functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

double qpp::rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

bigint qpp::rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx qpp::randidx (idx a=std::numeric_limits < idx >::min(), idx b=std::numeric_limits < idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

• template<typename Derived >

Derived qpp::rand (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double a QPP_UNUSED_=0, double b QPP_UNUSED_=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

template<>

dmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

• template<>

cmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived qpp::randn (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double mean QPP_UNUSED_=0, double sigma QPP_UNUSED_=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

dmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

• template<>

cmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

double qpp::randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

cmat qpp::randU (idx D=2)

Generates a random unitary matrix.

cmat qpp::randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > qpp::randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat qpp::randH (idx D=2)

Generates a random Hermitian matrix.

ket qpp::randket (idx D=2)

Generates a random normalized ket (pure state vector)

• cmat qpp::randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > qpp::randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > qpp::randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.


8.28.1 Detailed Description

Randomness-related functions.

8.29 statistics.h File Reference

Statistics functions.

This graph shows which files directly or indirectly include this file:



8.30 traits.h File Reference 417

Namespaces

• qpp

Quantum++ main namespace.

Functions

std::vector< double > qpp::uniform (idx N)

Uniform probability distribution vector.

std::vector< double > qpp::marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > qpp::marginalY (const dmat &probXY)

Marginal distribution.

• template<typename Container >

double qpp::avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_ \leftarrow iterable< Container >::value >::type *=nullptr)

Average.

 $\bullet \ \ \text{template}{<} \text{typename Container} >$

double qpp::cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Covariance.

• template<typename Container >

double qpp::var (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_← iterable< Container >::value >::type *=nullptr)

Variance.

• template<typename Container >

double qpp::sigma (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_ \leftarrow iterable< Container >::value >::type *=nullptr)

Standard deviation.

• template<typename Container >

double qpp::cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if is_iterable Container >::value >::type *=nullptr)

Correlation.


8.29.1 Detailed Description

Statistics functions.

8.30 traits.h File Reference

Type traits.

This graph shows which files directly or indirectly include this file:



Classes

```
struct qpp::make_void < Ts >
```

Helper for qpp::to_void<> alias template.

- struct qpp::is_iterable < T, typename >

Checks whether T is compatible with an STL-like iterable container.

• struct qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(*(std::declval < T >().end()), decltyp

struct qpp::is_matrix_expression< Derived >

Checks whether the type is an Eigen matrix expression.

struct qpp::is_complex< T >

Checks whether the type is a complex type.

struct qpp::is_complex< std::complex< T >>

Checks whether the type is a complex number type, specialization for complex types.

Namespaces

• qpp

Quantum++ main namespace.

Typedefs

```
    template<typename... Ts>
    using qpp::to_void = typename make_void< Ts... >::type
        Alias template that implements the proposal for void_t.
```


8.30.1 Detailed Description

Type traits.

8.31 types.h File Reference

Type aliases.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Typedefs

• using qpp::idx = std::size_t

Non-negative integer index, make sure you use an unsigned type.

• using qpp::bigint = long long int

Big integer.

• using qpp::cplx = std::complex < double >

Complex number in double precision.

• using qpp::ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector.

• using qpp::bra = Eigen::RowVectorXcd

Complex (double precision) dynamic Eigen row vector.

• using qpp::cmat = Eigen::MatrixXcd

Complex (double precision) dynamic Eigen matrix.

using qpp::dmat = Eigen::MatrixXd

Real (double precision) dynamic Eigen matrix.

 $\bullet \ \ \text{template}{<} \text{typename Scalar} >$

```
using \ qpp:: dyn\_mat = Eigen:: Matrix < Scalar, \ Eigen:: Dynamic, \ Eigen:: Dynamic > \\
```

Dynamic Eigen matrix over the field specified by Scalar.

template<typename Scalar >

```
using qpp::dyn_col_vect = Eigen::Matrix < Scalar, Eigen::Dynamic, 1 >
```

Dynamic Eigen column vector over the field specified by Scalar.

template<typename Scalar >

```
using qpp::dyn_row_vect = Eigen::Matrix< Scalar, 1, Eigen::Dynamic >
```

Dynamic Eigen row vector over the field specified by Scalar.

8.31.1 Detailed Description

Type aliases.

8.32 /Users/vlad/qpp/README.md File Reference

Index

/Users/vlad/qpp/README.md, 420	qpp::QCircuit, 286, 309
~Bit_circuit	all
qpp::Bit_circuit, 134	qpp::Dynamic_bitset, 163
~Codes	anticomm
qpp::Codes, 141	qpp, <mark>33</mark>
~Dynamic_bitset	any
qpp::Dynamic_bitset, 163	qpp::Dynamic_bitset, 163
~Gates	apply
qpp::Gates, 178	qpp, 33–35
~IDisplay	applyCTRL
qpp::IDisplay, 193	qpp, 36
~IJSON	applyQFT
qpp::IJSON, 195	qpp, 3 7
~ILayout	applyTFQ
•	
qpp::ILayout, 196 ∼Init	qpp, 37
-	avg
qpp::Init, 199	qpp, 38
~NoiseBase	h00
qpp::NoiseBase< T >, 251	b00
~QCircuit	qpp::States, 358
qpp::QCircuit, 284	b01
\sim QEngine	qpp::States, 359
qpp::QEngine, 317	b10
\sim RandomDevices	qpp::States, 359
qpp::RandomDevices, 343	b11
\sim Singleton	qpp::States, 359
qpp::internal::Singleton< T >, 347	bCNOT_
\sim States	qpp::Bit_circuit, 138
qpp::States, 356	begin
~Timer	qpp::QCircuit, 286
qpp::Timer< T, CLOCK_T >, 366	bFRED_
	qpp::Bit_circuit, 138
A_	bigint
qpp::internal::IOManipEigen, 203	qpp, 28
abs chop	Bit circuit
qpp::internal, 122	qpp::Bit_circuit, 133
absm	bloch2rho
qpp, 31	qpp, 38
abssq	bNOT
qpp, 31, 32	qpp::Bit_circuit, 138
add_circuit	
qpp::QCircuit, 284, 308	bra
add dit	qpp, 29
_	bSWAP_
qpp::QCircuit, 285	qpp::Bit_circuit, 138
add_hash_	bTOF_
qpp::QCircuit, 285	qpp::Bit_circuit, 138
add_qudit	btotal_
qpp::QCircuit, 285	qpp::Bit_circuit, 138
adjoint	
qpp, 32	c_reg_

qpp::QCircuit::MeasureStep, 245 cbegin		classes/circuits/engines.h, 382 classes/codes.h, 383
qpp::QCircuit, 287		classes/exception.h, 383
cCTRL		classes/gates.h, 385
qpp::QCircuit, 287, 288		classes/idisplay.h, 386
cCTRL_custom		classes/init.h, 387
qpp::QCircuit, 289		classes/layouts.h, 388
		<u>-</u>
cend		classes/noise.h, 389
qpp::QCircuit, 290		classes/random_devices.h, 390
check_cvector		classes/reversible.h, 390
qpp::internal, 122		classes/states.h, 391
check_dims		classes/timer.h, 392
qpp::internal, 123		cmat
check_dims_match_cvect		qpp, <mark>29</mark>
qpp::internal, 123		cmat_hash_tbl_
check_dims_match_mat		qpp::QCircuit, 311
qpp::internal, 123		CNOT
check_dims_match_rvect		qpp::Bit_circuit, 134
qpp::internal, 123		qpp::Gates, 186
check_eq_dims		CNOTba
qpp::internal, 123		qpp::Gates, 186
check_matching_sizes		Codes
qpp::internal, 123		qpp::Codes, 141
		codeword
check_no_duplicates		
qpp::internal, 124		qpp::Codes, 141
check_nonzero_size		comm
qpp::internal, 124		qpp, 40
check_perm		complement
qpp::internal, 124		qpp, 40
check_qubit_cvector		compperm
qpp::internal, 124		qpp, 41
check_qubit_matrix		compute_
qpp::internal, 124		qpp::Lattice, 224
check_qubit_rvector		compute_probs_
qpp::internal, 124		qpp::NoiseBase< T >, 251
check_qubit_vector		compute state
qpp::internal, 125		qpp::NoiseBase< T >, 251
check rvector		concurrence
qpp::internal, 125		qpp, 41
check_square_mat		conjugate
qpp::internal, 125		
** *		qpp, 41
check_subsys_match_dims		const_iterator
qpp::internal, 125		qpp::QCircuit, 282
check_vector		constants.h, 393
qpp::internal, 125		contfrac2x
choi2kraus		qpp, <mark>42</mark>
qpp, 39		convergents
choi2super		qpp, 42, 43
qpp, 39		cor
chop		qpp, 43
qpp, 118		cosm
chop_		qpp, 44
qpp::internal::IOManipEigen, 204		count
qpp::internal::IOManipPointer< Poir		qpp::Dynamic_bitset, 163
206		count
		qpp::Bit_circuit, 138
210	itIterator $>$,	qpp::QCircuit, 312
classes/circuits/circuits.h, 381		COV

qpp, 44 cplx qpp, 29 CTRL qpp::Gates, 179 qpp::QCircuit, 290, 291 ctrl_ qpp::QCircuit::GateStep, 190	qpp::exception::PermMismatchDims, 276 qpp::exception::QuditAlreadyMeasured, 338 qpp::exception::SizeMismatch, 349 qpp::exception::SubsysMismatchDims, 364 qpp::exception::TypeMismatch, 370 qpp::exception::UndefinedType, 372 qpp::exception::Unknown, 374 qpp::exception::ZeroSize, 380
CTRL_custom	det
qpp::QCircuit, 292	qpp, 45
CUSTOM	difference_type
qpp::QCircuit, 282	qpp::QCircuit::iterator, 218
CUSTOM_cCTRL qpp::QCircuit, 282	dims_ qpp::Lattice, 227
CUSTOM_CTRL	dirsum
qpp::QCircuit, 282	qpp, 45–47
CustomException	dirsum2
qpp::exception::CustomException, 143	qpp::internal, 125
cwise	dirsumpow
qpp, 45	qpp, 47
CZ	disp
qpp::Gates, 186	qpp, 48–50
	display
d_ consultaine Penns < T > .055	qpp::Dynamic_bitset, 164
<pre>qpp::NoiseBase< T >, 255 qpp::QCircuit, 312</pre>	qpp::IDisplay, 193
data	qpp::internal::IOManipEigen, 203
qpp::Dynamic_bitset, 163	<pre>qpp::internal::IOManipPointer< PointerType >,</pre>
depth_	206 qpp::internal::IOManipRange< InputIterator >,
qpp::Bit_circuit, 139	qpp::internal::iOManipHange< inputiterator >,
description	qpp::QCircuit, 292
qpp::exception::CustomException, 144	qpp::QCircuit::iterator::value_type_, 377
qpp::exception::DimsInvalid, 146	qpp::QEngine, 317
qpp::exception::DimsMismatchCvector, 148	qpp::Timer< T, CLOCK_T >, 367
qpp::exception::DimsMismatchMatrix, 150	display_impl_
qpp::exception::DimsMismatchRvector, 152	qpp::internal::Display_Impl_, 157
qpp::exception::DimsMismatchVector, 154	dits_
qpp::exception::DimsNotEqual, 156 qpp::exception::Duplicates, 159	qpp::QEngine::state_, 352
app::exception::Exception, 175	dmat
qpp::exception::InvalidIterator, 201	qpp, 29
qpp::exception::MatrixMismatchSubsys, 229	dyn_col_vect
qpp::exception::MatrixNotCvector, 231	qpp, 29 dyn_mat
qpp::exception::MatrixNotRvector, 233	qpp, 29
qpp::exception::MatrixNotSquare, 235	dyn_row_vect
qpp::exception::MatrixNotSquareNorCvector, 237	qpp, 30
qpp::exception::MatrixNotSquareNorRvector, 239	Dynamic_bitset
qpp::exception::MatrixNotSquareNorVector, 241	qpp::Dynamic_bitset, 162
qpp::exception::MatrixNotVector, 243	
qpp::exception::NoCodeword, 247	66
qpp::exception::NotBipartite, 258	qpp, 118
<pre>app::exception::NotImplemented, 260 app::exception::NotQubitCvector, 262</pre>	egcd
qpp::exception::NotQubitOvector, 262 qpp::exception::NotQubitMatrix, 264	qpp, 50 eig
app::exception::NotQubitMatrix, 264	qpp, 51
qpp::exception::NotQubitNvector, 256	elem_
qpp::exception::NotQubitVector, 270	qpp::QCircuit::iterator, 222
qpp::exception::OutOfRange, 272	end
qpp::exception::PermInvalid, 274	qpp::QCircuit, 293

end_	expm
<pre>qpp::internal::IOManipPointer< PointerType >, 207</pre>	qpp, 54
<pre>qpp::internal::IOManipRange< InputIterator >, 210</pre>	factors qpp, 54
qpp::Timer< T, CLOCK T>, 368	FAN
entanglement qpp, 51, 52	qpp::QCircuit, 282 Fd
entanglement.h, 394	qpp::Gates, 181
entropies.h, 396	fill_Ks_
entropy	qpp::QuditDepolarizingNoise, 341
qpp, 52	fill_probs_
evals	qpp::QuditDepolarizingNoise, 341
qpp, 53	first_
evects	qpp::internal::IOManipRange< InputIterator >,
qpp, 53	210
Exception	FIVE_QUBIT
qpp::exception::DimsInvalid, 146	qpp::Codes, 140
qpp::exception::DimsMismatchCvector, 148	flip
qpp::exception::DimsMismatchMatrix, 150	qpp::Dynamic_bitset, 164
qpp::exception::DimsMismatchRvector, 152	FRED
qpp::exception::DimsMismatchVector, 154	qpp::Bit_circuit, 134
qpp::exception::DimsNotEqual, 156	qpp::Gates, 186
qpp::exception::Duplicates, 159	functions.h, 397
qpp::exception::Exception, 175	funm
qpp::exception::InvalidIterator, 201	qpp, 54
qpp::exception::MatrixMismatchSubsys, 229	
qpp::exception::MatrixNotCvector, 231	GATE
	qpp::QCircuit, 283
qpp::exception::MatrixNotRvector, 233	gate
qpp::exception::MatrixNotSquare, 235	qpp::QCircuit, 293, 294
qpp::exception::MatrixNotSquareNorCvector, 237	gate_custom
qpp::exception::MatrixNotSquareNorRvector, 239	qpp::QCircuit, 295
qpp::exception::MatrixNotSquareNorVector, 241	gate_fan
qpp::exception::MatrixNotVector, 243	qpp::QCircuit, 295, 296
app::exception::NoCodeword, 247	gate_hash_
qpp::exception::NotBipartite, 258	qpp::QCircuit::GateStep, 190
app::exception::NotImplemented, 260	gate_type_
qpp::exception::NotQubitCvector, 262	qpp::QCircuit::GateStep, 191
qpp::exception::NotQubitMatrix, 264	Gates
qpp::exception::NotQubitRvector, 266	qpp::Gates, 178
qpp::exception::NotQubitSubsys, 268	gates_
qpp::exception::NotQubitVector, 270	qpp::QCircuit, 312
qpp::exception::OutOfRange, 272	gates_ip_
qpp::exception::PermInvalid, 274	qpp::QCircuit::iterator::value_type_, 377
qpp::exception::PermMismatchDims, 276	GateStep
qpp::exception::QuditAlreadyMeasured, 339	qpp::QCircuit::GateStep, 190
qpp::exception::SizeMismatch, 349	GateType
qpp::exception::SubsysMismatchDims, 364	qpp::QCircuit, 282
qpp::exception::TypeMismatch, 370	gcd
qpp::exception::UndefinedType, 372	qpp, 55
qpp::exception::Unknown, 374	gconcurrence
qpp::exception::ZeroSize, 380	qpp, 56
execute	generated_
qpp::QEngine, 318	qpp::NoiseBase< T >, 255
qpp::QNoisyEngine < NoiseModel >, 326, 327	get
expandout	qpp::Dynamic_bitset, 165
qpp::Gates, 179–181	get_circuit
experimental/experimental.h, 397	qpp::QEngine, 319

get_cmat_hash_tbl_	get_prng
qpp::QCircuit, 296	qpp::RandomDevices, 344
get_d	get_probs
qpp::NoiseBase< T >, 252	qpp::NoiseBase< T >, 253
qpp::QCircuit, 296	qpp::QEngine, 320
get_depth	get_psi
qpp::QCircuit, 297	qpp::QEngine, 320
get_dim_subsys	get_relative_pos_
qpp::internal, 126	qpp::QEngine, 321
get_dims	get_stats
qpp::ILayout, 196	qpp::QEngine, 321
qpp::Lattice, 225	get_step_count
get_dit	qpp::QCircuit, 300
qpp::QEngine, 319	get_thread_local_instance
get_dits	qpp::internal::Singleton $<$ T $>$, 347
qpp::QEngine, 319	GHZ
get_duration	qpp::States, 359
qpp::Timer< T, CLOCK_T >, 367	grams
get_gate_count	qpp, 56, 57
qpp::Bit_circuit, 135	
qpp::QCircuit, 297	Н
get_gate_depth	qpp::Gates, 187
qpp::Bit circuit, 135	hash_combine
get_gates_	qpp::internal, 126
qpp::QCircuit, 298	hash_eigen
get_instance	qpp, 57
	heig
qpp::internal::Singleton< T >, 347	qpp, 58
get_Ks	hevals
qpp::NoiseBase< T >, 252	qpp, 58
get_last_idx	hevects
qpp::NoiseBase< T >, 252	qpp, 59
get_last_K	
qpp::NoiseBase< T >, 253	i_
get_last_p	qpp::NoiseBase< T >, 255
qpp::NoiseBase< T >, 253	ld
get_measured	qpp::Gates, 182
qpp::QCircuit, 298	ld2
qpp::QEngine, 319, 320	qpp::Gates, 187
get_measurement_count	idx
qpp::QCircuit, 298, 299	qpp, 30
get_measurements_	index
qpp::QCircuit, 299	qpp::Dynamic_bitset, 165
get_name	infty
qpp::Gates, 182	qpp, 118
qpp::QCircuit, 299	Init
get_nc	qpp::Init, 199
qpp::QCircuit, 299	input_output.h, 402
get_noise_results	
qpp::QNoisyEngine < NoiseModel >, 327	instruments.h, 403
	internal/classes/iomanip.h, 405
get_non_measured	internal/classes/singleton.h, 406
qpp::QCircuit, 300	internal/util.h, 406
qpp::QEngine, 320	internal::Singleton< const Codes >
get_nop_count	qpp::Codes, 141
qpp::QCircuit, 300	internal::Singleton< const Gates >
get_nq	qpp::Gates, 186
qpp::QCircuit, 300	internal::Singleton $<$ const Init $>$
get_num_subsys	qpp::Init, 199
qpp::internal, 126	internal::Singleton $<$ const States $>$

qpp::States, 358	logm
internal::Singleton < RandomDevices >	qpp, 69
qpp::RandomDevices, 345	lognegativity
inverse	qpp, 69, 70
qpp, 59	. 177
invperm	marginalX
qpp, 60	qpp, 70
IOManipEigen	marginalY
qpp::internal::IOManipEigen, 203	qpp, 70 MATLAB/matlab.h, 408
IOManipPointer	
qpp::internal::IOManipPointer< PointerType >,	mats_hash_
205, 206	qpp::QCircuit::MeasureStep, 245
IOManipRange	maxn
qpp::internal::IOManipRange< InputIterator >,	qpp, 118
209	measure qpp, 71–75
ip	measure_seq
qpp, 60, 61	qpp, 76, 77
ip_	MEASURE V
qpp::QCircuit::iterator::value_type_, 378	qpp::QCircuit, 283
isprime	MEASURE V MANY
qpp, 61	qpp::QCircuit, 283
iterator	MEASURE Z
qpp::QCircuit::iterator, 219	qpp::QCircuit, 283
iterator_category	MEASURE_Z_MANY
qpp::QCircuit::iterator, 218	qpp::QCircuit, 283
jn	measured
qpp::States, 356	qpp::QCircuit, 312
qppotates, 000	MEASUREMENT
ket	qpp::QCircuit, 283
qpp, 30	measurement count
kraus2choi	qpp::QCircuit, 312
qpp, 61	measurement type
kraus2super	qpp::QCircuit::MeasureStep, 245
qpp, 62	measurements_
kron	qpp::QCircuit, 312
qpp, 62, 64, 65	measurements_ip_
qpp::QCircuit, 301, 309	qpp::QCircuit::iterator::value_type_, 378
kron2	MeasureStep
qpp::internal, 126	qpp::QCircuit::MeasureStep, 245
kronpow	MeasureType
qpp, 65	qpp::QCircuit, 282
Ks_	measureV
qpp::NoiseBase< T >, 255	qpp::QCircuit, 302
	measureZ
last_	qpp::QCircuit, 303
qpp::internal::IOManipRange< InputIterator >,	mes
210	qpp::States, 356
Lattice	minus
qpp::Lattice, 224	qpp::States, 357
lcm	mket
qpp, 66	qpp, 77, 78
load	modinv
qpp, 67	qpp, 78
qpp::RandomDevices, 344	MODMUL
loadMATLAB	qpp::Gates, 183
qpp, 67, 68	modmul
logdet	qpp, 79
qpp, 68	modpow

qpp, 79	number_theory.h, 409
mprj qpp, 80	offset_
msg_	qpp::Dynamic_bitset, 166
qpp::exception::Exception, 176	omega qpp, 83
multiidx2n	
qpp, 81	one
qpp::internal, 127	qpp::States, 357
MULTIPLE_cCTRL_MULTIPLE_TARGET	operations.h, 411
qpp::QCircuit, 282	operator *
MULTIPLE_cCTRL_SINGLE_TARGET	qpp::QCircuit::iterator, 219
qpp::QCircuit, 282	operator!=
MULTIPLE_CTRL_MULTIPLE_TARGET	qpp::Dynamic_bitset, 166
qpp::QCircuit, 282	qpp::QCircuit::iterator, 220
MULTIPLE_CTRL_SINGLE_TARGET	operator<<
qpp::QCircuit, 282	qpp::IDisplay, 194
qppconcuit, 202	qpp::QCircuit, 309, 310
n2multiidx	operator()
qpp, 81	qpp::ILayout, 197
qpp::internal, 127	
	qpp::internal::EqualEigen, 171
N_	qpp::internal::EqualSameSizeStringDits, 172
qpp::internal::IOManipPointer< PointerType >,	qpp::internal::HashEigen, 192
207	qpp::Lattice, 225
n_	qpp::NoiseBase< T >, 253, 254
qpp::Dynamic_bitset, 170	operator++
name_	qpp::QCircuit::iterator, 220
qpp::QCircuit, 313	operator-
qpp::QCircuit::GateStep, 191	qpp::Dynamic_bitset, 166
qpp::QCircuit::MeasureStep, 246	operator=
nc_	<pre>qpp::internal::IOManipPointer< PointerType >,</pre>
qpp::QCircuit, 313	206
negativity	
	qpp::internal::IOManipRange< InputIterator >,
qpp, 82	210
NINE_QUBIT_SHOR	qpp::internal::Singleton $<$ T $>$, 347
qpp::Codes, 140	qpp::QCircuit::iterator, 220
noise_	<pre>qpp::QCircuit::iterator::value_type_, 377</pre>
qpp::QNoisyEngine < NoiseModel >, 328	qpp::QEngine, 321
noise_results_	qpp::QEngine::state_, 351
qpp::QNoisyEngine < NoiseModel >, 328	operator==
noise_type	qpp::Dynamic bitset, 167
qpp::NoiseBase< T >, 250	qpp::QCircuit::iterator, 221
NoiseBase	operator""_bra
qpp::NoiseBase< T >, 250	gpp::literals, 128
NONE	operator""_i
qpp::QCircuit, 282, 283	• —
none	qpp::literals, 128, 129
	operator""_if
qpp::Dynamic_bitset, 165	qpp::literals, 129
NOP	operator""_ket
qpp::QCircuit, 283	qpp::literals, 129
nop	operator""_prj
qpp::QCircuit, 303	qpp::literals, 130
norm	
qpp, 83	p_
normalize	<pre>qpp::internal::IOManipPointer< PointerType >,</pre>
qpp, 83	207
NOT	pb00
gpp::Bit circuit, 136	qpp::States, 359
nq_	pb01
qpp::QCircuit, 313	qpp::States, 359
Abburgoulouit, o to	4ppotatoo, 000

pb10	qpp::QCircuit, 311
qpp::States, 360	qpp::QEngine, 316, 317
pb11	QFT
qpp::States, 360	qpp, 90
pGHZ	qpp::QCircuit, 304, 305
qpp::States, 360	qmutualinfo
pi	qpp, 90, 91
qpp, 118 plus	QNoisyEngine
qpp::States, 357	qpp::QNoisyEngine < NoiseModel >, 326 qpp, 15
pointer	absm, 31
qpp::QCircuit::iterator, 218	abssq, 31, 32
powm	adjoint, 32
qpp, 84	anticomm, 33
prj	apply, 33–35
qpp, 84	applyCTRL, 36
prng_	applyQFT, 37
qpp::RandomDevices, 345	applyTFQ, 37
PROB	avg, 38
qpp, 31 probs_	bigint, 28
qpp::NoiseBase< T >, 255	bloch2rho, 38
qpp::QEngine::state_, 352	bra, 29
prod	choi2kraus, 39
qpp, 85	choi2super, 39 chop, 118
prod_dims	cmat, 29
qpp::Lattice, 226	comm, 40
psi_	complement, 40
qpp::QEngine::state_, 352	compperm, 41
ptrace	concurrence, 41
qpp, 86	conjugate, 41
ptrace1	contfrac2x, 42
qpp, 87	convergents, 42, 43
ptrace2	cor, 43
qpp, 88 ptranspose	cosm, 44
qpp, 89	cov, 44
pW	cplx, 29
qpp::States, 360	cwise, 45
px0	det, 45
qpp::States, 360	dirsum, 45–47 dirsumpow, 47
px1	disp, 48–50
qpp::States, 360	dmat, 29
py0	dyn_col_vect, 29
qpp::States, 361	dyn_mat, 29
py1	dyn_row_vect, 30
qpp::States, 361	ee, 118
pz0 qpp::States, 361	egcd, 50
pz1	eig, 51
qpp::States, 361	entanglement, 51, 52
и т	entropy, 52
qc_	evals, 53
qpp::QCircuit::iterator, 222	evects, 53
app::QEngine, 323	expm, 54
qpp::QEngine::state_, 352	factors, 54
QCircuit	funm, 54
qpp::QCircuit, 283 QEngine	gcd, 55 gconcurrence, 56
- A⊏HAIHE	goonoun ence, 30

grams, 56, 57	randrho, 99
hash_eigen, 57	randU, 99
heig, 58	randV, 100
hevals, 58	renyi, 100, 101
hevects, 59	RES, 31
idx, 30	reshape, 101
infty, 118	rho2bloch, 102
inverse, 59	rho2pure, 102
invperm, 60	save, 103
ip, 60, 61	saveMATLAB, 103, 104
isprime, 61	schatten, 104
ket, 30	schmidtA, 105
kraus2choi, 61	schmidtB, 105, 106
kraus2super, 62	schmidtcoeffs, 106, 107
kron, 62, 64, 65	schmidtprobs, 107, 108
kronpow, 65	sigma, 108
Icm, 66	sinm, 109
load, 67	spectralpowm, 109
loadMATLAB, 67, 68	sqrtm, 110
logdet, 68	ST, 31
logm, 69	sum, 110, 111
lognegativity, 69, 70	super2choi, 111
marginalX, 70	svals, 112
marginalY, 70	svd, 112
maxn, 118	svdU, 112
measure, 71–75	svdV, 113
measure_seq, 76, 77	syspermute, 113, 114
mket, 77, 78	TFQ, 114
modinv, 78	to_void, 30
modmul, 79	trace, 114
modpow, 79	transpose, 115
mprj, 80	tsallis, 115, 116
multiidx2n, 81	uniform, 116
n2multiidx, 81	var, 117
negativity, 82	x2contfrac, 117
norm, 83	qpp.h, 413
normalize, 83	QPP_UNUSED_, 414
omega, 83	qpp::Bit_circuit, 131
pi, 118	\sim Bit_circuit, 134
powm, 84	bCNOT_, 138
prj, 84	bFRED_, 138
PROB, 31	Bit_circuit, 133
prod, 85	bNOT_, 138
ptrace, 86	bSWAP_, 138
ptrace1, 87	bTOF_, 138
ptrace2, 88	btotal_, 138
ptranspose, 89	CNOT, 134
QFT, 90	count_, 138
qmutualinfo, 90, 91	depth_, 139
rand, 91-93	FRED, 134
randH, 94	get_gate_count, 135
randidx, 94	get_gate_depth, 135
randket, 94	NOT, 136
randkraus, 95	reset, 136
randn, 95–97	SWAP, 136
randperm, 97	TOF, 137
randprime, 97	X, 137
randprob, 99	qpp::Codes, 139

\sim Codes, 141	qpp::exception::Duplicates, 158
Codes, 141	description, 159
codeword, 141	Exception, 159
FIVE_QUBIT, 140	qpp::exception::Exception, 173
internal::Singleton < const Codes >, 141	description, 175
NINE_QUBIT_SHOR, 140	Exception, 175
SEVEN_QUBIT_STEANE, 140	msg_, 176
Type, 140	what, 175
qpp::Dynamic_bitset, 159	where_, 176
\sim Dynamic_bitset, 163	qpp::exception::InvalidIterator, 200
all, 163	description, 201
any, 163	Exception, 201
count, 163	qpp::exception::MatrixMismatchSubsys, 228
data, 163	description, 229
display, 164	Exception, 229
Dynamic_bitset, 162	qpp::exception::MatrixNotCvector, 230
flip, 164	description, 231
get, 165	Exception, 231
index_, 165	qpp::exception::MatrixNotRvector, 232
n_, 170	description, 233
none, 165	Exception, 233
offset_, 166	qpp::exception::MatrixNotSquare, 234
operator!=, 166	description, 235
operator-, 166	Exception, 235
operator==, 167	qpp::exception::MatrixNotSquareNorCvector, 236
rand, 167, 168	description, 237
reset, 168	Exception, 237
set, 168, 169	qpp::exception::MatrixNotSquareNorRvector, 238
size, 169	description, 239
storage_size, 169	Exception, 239
storage_size_, 170	qpp::exception::MatrixNotSquareNorVector, 240
storage_type, 162	description, 241
to_string, 169	Exception, 241
v , 170	qpp::exception::MatrixNotVector, 242
value_type, 162	description, 243
qpp::exception, 118	Exception, 243
qpp::exception::CustomException, 142	qpp::exception::NoCodeword, 246
CustomException, 143	description, 247
description, 144	Exception, 247
what_, 144	qpp::exception::NotBipartite, 256
qpp::exception::DimsInvalid, 145	description, 258
description, 146	Exception, 258
Exception, 146	qpp::exception::NotImplemented, 258
qpp::exception::DimsMismatchCvector, 147	description, 260
description, 148	Exception, 260
Exception, 148	qpp::exception::NotQubitCvector, 260
qpp::exception::DimsMismatchMatrix, 149	description, 262
description, 150	Exception, 262
Exception, 150	qpp::exception::NotQubitMatrix, 262
qpp::exception::DimsMismatchRvector, 151	description, 264
description, 152	Exception, 264
Exception, 152	qpp::exception::NotQubitRvector, 264
qpp::exception::DimsMismatchVector, 153	description, 266
description, 154	Exception, 266
Exception, 154	qpp::exception::NotQubitSubsys, 266
qpp::exception::DimsNotEqual, 155	description, 268
description, 156	Exception, 268
Exception, 156	qpp::exception::NotQubitVector, 268
-1 /	II

description, 270	X, 188
Exception, 270	Xd, 185
qpp::exception::OutOfRange, 270	Y, 188
description, 272	Z, 188
Exception, 272	Zd, 185
qpp::exception::PermInvalid, 272	qpp::IDisplay, 192
description, 274	∼IDisplay, 193
Exception, 274	display, 193
qpp::exception::PermMismatchDims, 274	operator<<, 194
description, 276	qpp::IJSON, 194
Exception, 276	~IJSON, 195
qpp::exception::QuditAlreadyMeasured, 337	to_JSON, 195
description, 338	qpp::ILayout, 195
Exception, 339	~ILayout, 196
qpp::exception::SizeMismatch, 348	get_dims, 196
description, 349	operator(), 197
Exception, 349	to_coordinates, 197
qpp::exception::SubsysMismatchDims, 363	qpp::Init, 198
description, 364 Exception, 364	~Init, 199
•	Init, 199
<pre>qpp::exception::TypeMismatch, 369 description, 370</pre>	internal::Singleton< const Init >, 199 qpp::internal, 120
Exception, 370	abs_chop, 122
qpp::exception::UndefinedType, 371	check_cvector, 122
description, 372	check_dims, 123
Exception, 372	check_dims_match_cvect, 123
app::exception::Unknown, 373	check_dims_match_mat, 123
description, 374	check_dims_match_rvect, 123
Exception, 374	check_eq_dims, 123
qpp::exception::ZeroSize, 379	check_matching_sizes, 123
description, 380	check_no_duplicates, 124
Exception, 380	check_nonzero_size, 124
qpp::experimental, 120	check_perm, 124
qpp::Gates, 176	check_qubit_cvector, 124
∼Gates, 178	check qubit matrix, 124
CNOT, 186	check_qubit_rvector, 124
CNOTba, 186	check_qubit_vector, 125
CTRL, 179	check rvector, 125
CZ, 186	check_square_mat, 125
expandout, 179–181	check subsys match dims, 125
Fd, 181	check vector, 125
FRED, 186	dirsum2, 125
Gates, 178	get_dim_subsys, 126
get_name, 182	get_num_subsys, 126
H, 187	hash_combine, 126
ld, 182	kron2, 126
ld2, 187	multiidx2n, 127
internal::Singleton < const Gates >, 186	n2multiidx, 127
MODMUL, 183	variadic_vector_emplace, 127
Rn, 183	qpp::internal::Display_Impl_, 157
RX, 184	display_impl_, 157
RY, 184	qpp::internal::EqualEigen, 171
RZ, 184	operator(), 171
S, 187	qpp::internal::EqualSameSizeStringDits, 172
SWAP, 187	operator(), 172
SWAPd, 185	qpp::internal::HashEigen, 191
T, 187	operator(), 192
TOF, 187	qpp::internal::IOManipEigen, 202

A_, 203	d_, 255
chop_, 204	generated_, 255
display, 203	get_d, 252
IOManipEigen, 203	get_Ks, 252
<pre>qpp::internal::IOManipPointer< PointerType >, 204</pre>	get_last_idx, 252
chop_, 206	get_last_K, <mark>253</mark>
display, 206	get_last_p, 253
end_, 207	get probs, 253
IOManipPointer, 205, 206	i_, 255
·	Ks_, 255
N_, 207	
operator=, 206	noise_type, 250
p_, 207	NoiseBase, 250
separator_, 207	operator(), 253, 254
start_, 207	probs_, 255
qpp::internal::IOManipRange< InputIterator >, 208	qpp::NoiseType, 256
chop_, 210	<pre>qpp::NoiseType::StateDependent, 353</pre>
display, 209	<pre>qpp::NoiseType::StateIndependent, 353</pre>
end_, 210	qpp::QCircuit, 277
first_, 210	∼QCircuit, 284
IOManipRange, 209	add_circuit, 284, 308
last_, 210	add_dit, 285
operator=, 210	add_hash_, 285
separator_, 211	add_qudit, 285
start_, 211	adjoint, 286, 309
	-
qpp::internal::Singleton< T >, 345	begin, 286
∼Singleton, 347	cbegin, 287
get_instance, 347	cCTRL, 287, 288
get_thread_local_instance, 347	cCTRL_custom, 289
operator=, 347	cend, 290
Singleton, 346	cmat_hash_tbl_, 311
qpp::is_complex< std::complex< T >>, 212	const_iterator, 282
qpp::is_complex< T >, 211	count_, 312
<pre>qpp::is_iterable< T, to_void< decltype(std::declval<</pre>	CTRL, 290, 291
T >().begin()), decltype(std::declval< T	CTRL_custom, 292
>().end()), decltype(*(std::declval< T	CUSTOM, 282
>().begin()))> >, 214	CUSTOM_cCTRL, 282
qpp::is_iterable< T, typename >, 213	CUSTOM_CTRL, 282
qpp::is_matrix_expression< Derived >, 216	d_, 312
qpp::Lattice, 222	display, 292
	• •
compute_, 224	end, 293
dims_, 227	FAN, 282
get_dims, 225	GATE, 283
Lattice, 224	gate, 293, 294
operator(), 225	gate_custom, 295
prod_dims, 226	gate_fan, 295, 296
to_coordinates, 226	gates_, 312
qpp::literals, 128	GateType, 282
operator""_bra, 128	get_cmat_hash_tbl_, 296
operator""_i, 128, 129	get_d, 296
operator""_if, 129	get_depth, 297
operator""_ket, 129	get_gate_count, 297
operator""_prj, 130	get_gates_, 298
qpp::make_void< Ts >, 227	get_measured, 298
	- -
type, 227	get_measurement_count, 298, 299
qpp::NoiseBase< T >, 248	get_measurements_, 299
∼NoiseBase, 251	get_name, 299
compute_probs_, 251	get_nc, 299
compute_state_, 251	get_non_measured, 300

get_nop_count, 300	operator==, 221
get_nq, 300	pointer, 218
get_step_count, 300	qc_, 222
kron, 301, 309	reference, 219
MEASURE V, 283	set_begin_, 221
MEASURE_V_MANY, 283	set_end_, 221
MEASURE_Z, 283	value_type, 219
MEASURE_Z_MANY, 283	qpp::QCircuit::iterator::value type , 375
measured_, 312	display, 377
MEASUREMENT, 283	gates_ip_, 377
measurement_count_, 312	ip_, 378
measurements_, 312	measurements_ip_, 378
MeasureType, 282	operator=, 377
measureV, 302	type_, 378
measureZ, 303	value_type_, 376, 377
MULTIPLE_cCTRL_MULTIPLE_TARGET, 282	value_type_qc_, 378
MULTIPLE_cCTRL_SINGLE_TARGET, 282	qpp::QCircuit::MeasureStep, 244
MULTIPLE_CTRL_MULTIPLE_TARGET, 282	c_reg_, 245
MULTIPLE_CTRL_SINGLE_TARGET, 282	mats_hash_, 245
name_, 313	measurement_type_, 245
nc_, 313	MeasureStep, 245
NONE, 282, 283	name_, 246
NOP, 283	target_, 246
nop, 303	qpp::QEngine, 314
·	~QEngine, 317
nq_, 313	-
operator<<, 309, 310	display, 317
QCircuit, 283	execute, 318
QEngine, 311	get_circuit, 319
QFT, 304, 305	get_dit, 319
replicate, 305, 311	get_dits, 319
SINGLE, 282	get_measured, 319, 320
SINGLE_cCTRL_MULTIPLE_TARGET, 282	get_non_measured, 320
SINGLE_cCTRL_SINGLE_TARGET, 282	get_probs, 320
SINGLE_CTRL_MULTIPLE_TARGET, 282	get_psi, 320
SINGLE_CTRL_SINGLE_TARGET, 282	get_relative_pos_, 321
step_types_, 313	get_stats, 321
StepType, 283	operator=, 321
TFQ, 305, 307	qc , 323
THREE, 282	QEngine, 316, 317
to_JSON, 307	reset, 321
TWO, 282	reset_stats, 322
qpp::QCircuit::GateStep, 189	set_dit, 322
ctrl_, 190	set measured , 322
	— — — — — — — — — — — — — — — — — — —
gate_hash_, 190	set_psi, 323
gate_type_, 191	st_, 324
GateStep, 190	stats_, 324
name_, 191	to_JSON, 323
shift_, 191	qpp::QEngine::state_, 350
target_, 191	dits_, 352
qpp::QCircuit::iterator, 217	operator=, 351
difference_type, 218	probs_, 352
elem_, 222	psi_, 352
iterator, 219	qc_, 352
iterator_category, 218	reset, 351
operator *, 219	state_, 351
operator!=, 220	subsys_, 352
operator++, 220	qpp::QNoisyEngine < NoiseModel >, 324
operator=, 220	execute, 326, 327
1 / -	,, -

get_noise_results, 327	y0, <mark>362</mark>
noise_, 328	y1, 362
noise_results_, 328	z0, 362
QNoisyEngine, 326	z1, 362
qpp::QubitAmplitudeDampingNoise, 328	zero, 358
QubitAmplitudeDampingNoise, 329	qpp::Timer < T, CLOCK_T >, 365
qpp::QubitBitFlipNoise, 330	\sim Timer, 366
QubitBitFlipNoise, 331	display, 367
qpp::QubitBitPhaseFlipNoise, 331	end_, 368
QubitBitPhaseFlipNoise, 332	get_duration, 367
qpp::QubitDepolarizingNoise, 333	start_, 368
QubitDepolarizingNoise, 334	tic, 367
qpp::QubitPhaseDampingNoise, 334	tics, 368
QubitPhaseDampingNoise, 335	Timer, 366
qpp::QubitPhaseFlipNoise, 336	toc, 368
QubitPhaseFlipNoise, 337	QPP_UNUSED_
qpp::QuditDepolarizingNoise, 339	qpp.h, 414
fill_Ks_, 341	QubitAmplitudeDampingNoise
fill_probs_, 341	qpp::QubitAmplitudeDampingNoise, 329
QuditDepolarizingNoise, 340	QubitBitFlipNoise
qpp::RandomDevices, 342	qpp::QubitBitFlipNoise, 331
•••	QubitBitPhaseFlipNoise
~RandomDevices, 343	qpp::QubitBitPhaseFlipNoise, 332
get_prng, 344	QubitDepolarizingNoise
internal::Singleton< RandomDevices >, 345	qpp::QubitDepolarizingNoise, 334
load, 344	QubitPhaseDampingNoise
prng_, 345	qpp::QubitPhaseDampingNoise, 335
RandomDevices, 343	QubitPhaseFlipNoise
rd_, 345	qpp::QubitPhaseFlipNoise, 337
save, 344	QuditDepolarizingNoise
qpp::States, 353	qpp::QuditDepolarizingNoise, 340
\sim States, 356	qppquanbepoidnemgreoise, 040
b00, 358	rand
b01, 359	qpp, 91–93
b10, 359	qpp::Dynamic_bitset, 167, 168
	qpp::by:iai:iio_bitoot; 107; 100
b11, 359	randH
GHZ, 359	randH
GHZ, 359	randH qpp, 94 randidx
GHZ, 359 internal::Singleton < const States >, 358	randH qpp, 94
GHZ, 359 internal::Singleton< const States >, 358 jn, 356	randH qpp, 94 randidx qpp, 94 randket
GHZ, 359 internal::Singleton< const States >, 358 jn, 356 mes, 356	randH qpp, 94 randidx qpp, 94
GHZ, 359 internal::Singleton < const States >, 358 jn, 356 mes, 356 minus, 357	randH qpp, 94 randidx qpp, 94 randket qpp, 94 randkraus
GHZ, 359 internal::Singleton < const States >, 358 jn, 356 mes, 356 minus, 357 one, 357	randH qpp, 94 randidx qpp, 94 randket qpp, 94 randkraus qpp, 95
GHZ, 359 internal::Singleton < const States >, 358 jn, 356 mes, 356 minus, 357 one, 357 pb00, 359	randH qpp, 94 randidx qpp, 94 randket qpp, 94 randkraus qpp, 95 randn
GHZ, 359 internal::Singleton < const States >, 358 jn, 356 mes, 356 minus, 357 one, 357 pb00, 359 pb01, 359	randH qpp, 94 randidx qpp, 94 randket qpp, 94 randkraus qpp, 95 randn qpp, 95–97
GHZ, 359 internal::Singleton < const States >, 358 jn, 356 mes, 356 minus, 357 one, 357 pb00, 359 pb01, 359 pb10, 360	randH qpp, 94 randidx qpp, 94 randket qpp, 94 randkraus qpp, 95 randn qpp, 95–97 random.h, 415
GHZ, 359 internal::Singleton < const States >, 358 jn, 356 mes, 356 minus, 357 one, 357 pb00, 359 pb01, 359 pb10, 360 pb11, 360 pGHZ, 360	randH qpp, 94 randidx qpp, 94 randket qpp, 94 randkraus qpp, 95 randn qpp, 95–97 random.h, 415 RandomDevices
GHZ, 359 internal::Singleton < const States >, 358 jn, 356 mes, 356 minus, 357 one, 357 pb00, 359 pb01, 359 pb10, 360 pb11, 360 pGHZ, 360 plus, 357	randH qpp, 94 randidx qpp, 94 randket qpp, 94 randkraus qpp, 95 randn qpp, 95–97 random.h, 415 RandomDevices qpp::RandomDevices, 343
GHZ, 359 internal::Singleton < const States >, 358 jn, 356 mes, 356 minus, 357 one, 357 pb00, 359 pb01, 359 pb10, 360 pb11, 360 pGHZ, 360 plus, 357 pW, 360	randH qpp, 94 randidx qpp, 94 randket qpp, 94 randkraus qpp, 95 randn qpp, 95–97 random.h, 415 RandomDevices qpp::RandomDevices, 343 randperm
GHZ, 359 internal::Singleton < const States >, 358 jn, 356 mes, 356 minus, 357 one, 357 pb00, 359 pb01, 359 pb10, 360 pb11, 360 pGHZ, 360 plus, 357 pW, 360 px0, 360	randH qpp, 94 randidx qpp, 94 randket qpp, 94 randkraus qpp, 95 randn qpp, 95–97 random.h, 415 RandomDevices qpp::RandomDevices, 343 randperm qpp, 97
GHZ, 359 internal::Singleton < const States >, 358 jn, 356 mes, 356 minus, 357 one, 357 pb00, 359 pb01, 359 pb10, 360 pb11, 360 pGHZ, 360 plus, 357 pW, 360 px0, 360 px1, 360	randH
GHZ, 359 internal::Singleton < const States >, 358 jn, 356 mes, 356 minus, 357 one, 357 pb00, 359 pb01, 359 pb10, 360 pb11, 360 pGHZ, 360 plus, 357 pW, 360 px0, 360 px1, 360 py0, 361	randH
GHZ, 359 internal::Singleton< const States >, 358 jn, 356 mes, 356 mes, 357 one, 357 pb00, 359 pb01, 359 pb10, 360 pb11, 360 pGHZ, 360 plus, 357 pW, 360 px0, 360 px1, 360 py0, 361 py1, 361	randH
GHZ, 359 internal::Singleton < const States >, 358 jn, 356 mes, 356 minus, 357 one, 357 pb00, 359 pb01, 359 pb10, 360 pb11, 360 pGHZ, 360 plus, 357 pW, 360 px0, 360 px1, 360 py0, 361 py1, 361 pz0, 361	randH
GHZ, 359 internal::Singleton < const States >, 358 jn, 356 mes, 356 minus, 357 one, 357 pb00, 359 pb01, 359 pb10, 360 pb11, 360 pGHZ, 360 plus, 357 pW, 360 px0, 360 px1, 360 py0, 361 py1, 361 pz0, 361 pz1, 361	randH
GHZ, 359 internal::Singleton < const States >, 358 jn, 356 mes, 356 minus, 357 one, 357 pb00, 359 pb01, 359 pb10, 360 pb11, 360 pGHZ, 360 plus, 357 pW, 360 px0, 360 px1, 360 py0, 361 py1, 361 pz0, 361 pz1, 361 States, 356	randH
GHZ, 359 internal::Singleton < const States >, 358 jn, 356 mes, 356 mes, 357 one, 357 pb00, 359 pb01, 359 pb10, 360 pb11, 360 pGHZ, 360 plus, 357 pW, 360 px0, 360 px1, 360 py0, 361 py1, 361 pz0, 361 pz1, 361 States, 356 W, 361	randH
GHZ, 359 internal::Singleton < const States >, 358 jn, 356 mes, 356 minus, 357 one, 357 pb00, 359 pb01, 359 pb10, 360 pb11, 360 pGHZ, 360 plus, 357 pW, 360 px0, 360 px1, 360 py0, 361 py1, 361 pz0, 361 pz1, 361 States, 356	randH

qpp, 100	set_dit
rd_ qpp::RandomDevices, 345	qpp::QEngine, 322 set_end_
reference	qpp::QCircuit::iterator, 221
qpp::QCircuit::iterator, 219	set_measured_
renyi	qpp::QEngine, 322
qpp, 100, 101	set_psi
replicate	qpp::QEngine, 323
qpp::QCircuit, 305, 311	SEVEN_QUBIT_STEANE
RES	qpp::Codes, 140
qpp, 31 reset	shift_
qpp::Bit_circuit, 136	qpp::QCircuit::GateStep, 191 sigma
qpp::Dynamic_bitset, 168	qpp, 108
qpp::QEngine, 321	SINGLE
qpp::QEngine::state_, 351	qpp::QCircuit, 282
reset_stats	SINGLE_cCTRL_MULTIPLE_TARGET
qpp::QEngine, 322	qpp::QCircuit, 282
reshape	SINGLE_cCTRL_SINGLE_TARGET
qpp, 101 rho2bloch	qpp::QCircuit, 282
qpp, 102	SINGLE_CTRL_MULTIPLE_TARGET
rho2pure	qpp::QCircuit, 282
qpp, 102	SINGLE_CTRL_SINGLE_TARGET qpp::QCircuit, 282
Rn	Singleton
qpp::Gates, 183	qpp::internal::Singleton< T >, 346
RX	sinm
qpp::Gates, 184	qpp, 109
RY	size
qpp::Gates, 184 RZ	qpp::Dynamic_bitset, 169
qpp::Gates, 184	spectralpowm
	qpp, 109
S	sqrtm qpp, 110
qpp::Gates, 187	ST
save qpp, 103	qpp, 31
qpp::RandomDevices, 344	st_
saveMATLAB	qpp::QEngine, 324
qpp, 103, 104	start_
schatten	<pre>qpp::internal::IOManipPointer< PointerType >,</pre>
qpp, 104	207
schmidtA	qpp::internal::IOManipRange< InputIterator >, 211
qpp, 105	qpp::Timer< T, CLOCK_T >, 368
schmidtB	state
qpp, 105, 106 schmidtcoeffs	qpp::QEngine::state_, 351
qpp, 106, 107	States
schmidtprobs	qpp::States, 356
qpp, 107, 108	statistics.h, 416
separator_	stats_
qpp::internal::IOManipPointer< Pointe	
207	step_types_
qpp::internal::IOManipRange< InputIte	
211 set	StepType qpp::QCircuit, 283
qpp::Dynamic_bitset, 168, 169	storage_size
set_begin_	qpp::Dynamic_bitset, 169
qpp::QCircuit::iterator, 221	storage_size_

qpp::Dynamic_bitset, 170	traits.h, 417
storage_type	transpose
qpp::Dynamic_bitset, 162	qpp, 115
subsys_	tsallis
qpp::QEngine::state_, 352	qpp, 115, 116
sum	TWO
qpp, 110, 111	qpp::QCircuit, 282
super2choi	Туре
qpp, 111	qpp::Codes, 140
svals	type
qpp, 112	qpp::make_void< Ts >, 227
svd	type_
qpp, 112 svdU	qpp::QCircuit::iterator::value_type_, 378
	types.h, 419
qpp, 112 svdV	uniform
qpp, 113	qpp, 116
SWAP	ЧРР , 110
qpp::Bit circuit, 136	V_
qpp::Gates, 187	- qpp::Dynamic_bitset, 170
SWAPd	value_type
qpp::Gates, 185	qpp::Dynamic_bitset, 162
syspermute	qpp::QCircuit::iterator, 219
qpp, 113, 114	value_type_
	qpp::QCircuit::iterator::value_type_, 376, 377
Т	value_type_qc_
qpp::Gates, 187	<pre>qpp::QCircuit::iterator::value_type_, 378</pre>
target_	var
qpp::QCircuit::GateStep, 191	qpp, 117
qpp::QCircuit::MeasureStep, 246	variadic_vector_emplace
TFQ	qpp::internal, 127
qpp, 114	
qpp::QCircuit, 305, 307	W
THREE	qpp::States, 361
qpp::QCircuit, 282 tic	what
	qpp::exception::Exception, 175
qpp::Timer < T, CLOCK_T >, 367 tics	what_
qpp::Timer< T, CLOCK_T >, 368	qpp::exception::CustomException, 144
Timer	where_ qpp::exception::Exception, 176
qpp::Timer< T, CLOCK_T >, 366	qppexceptionexception, 176
to coordinates	X
qpp::ILayout, 197	qpp::Bit_circuit, 137
qpp::Lattice, 226	qpp::Gates, 188
to_JSON	x0
qpp::IJSON, 195	qpp::States, 361
qpp::QCircuit, 307	x1
qpp::QEngine, 323	qpp::States, 362
to_string	x2contfrac
qpp::Dynamic_bitset, 169	qpp, 117
to_void	Xd
qpp, 30	qpp::Gates, 185
toc	
qpp::Timer< T, CLOCK_T >, 368	Υ
TOF	qpp::Gates, 188
qpp::Bit_circuit, 137	у0
qpp::Gates, 187	qpp::States, 362
trace	y1
qpp, 114	qpp::States, 362

```
Z qpp::Gates, 188 z0 qpp::States, 362 z1 qpp::States, 362 Zd qpp::Gates, 185 zero qpp::States, 358
```