Quantum++ v1.1

Generated by Doxygen 1.8.14

Contents

1	Qua	ntum++																	1
2	Nam	nespace	space Index 3																
	2.1	Names	space List									 	 		 	 	 		 3
3	Hier	archica	l Index																5
	3.1	Class	Hierarchy									 	 		 	 	 		 5
4	Clas	s Index																	7
	4.1	Class	List									 	 		 	 	 		 7
5	File	Index																	11
	5.1	File Lis	st									 	 		 	 	 		 11
6	Nam	nespace	Docume	nta	tion														13
	6.1	qpp Na	amespace	Re	ferer	nce .						 	 		 		 		 13
		6.1.1	Detailed	De	scrip	tion						 	 		 	 	 		 26
		6.1.2	Typedef	Dod	cume	entati	on .					 	 		 	 	 		 26
			6.1.2.1	bi	igint							 	 		 	 	 		 26
			6.1.2.2	bı	ra .							 	 		 	 	 		 26
			6.1.2.3	CI	mat							 	 		 	 	 		 27
			6.1.2.4	c	plx .							 	 		 	 	 		 27
			6.1.2.5	dı	mat							 	 		 		 		 27
			6.1.2.6	dy	yn_c	ol_ve	ect .					 	 		 		 		 27
			6.1.2.7	dy	yn_m	nat .						 	 		 	 	 		 27
			6.1.2.8	d	vn ro	ow v	ect					 	 		 	 	 		 28

ii CONTENTS

	6.1.2.9	idx	28
	6.1.2.10	ket	28
	6.1.2.11	to_void	28
6.1.3	Function	Documentation	28
	6.1.3.1	absm()	28
	6.1.3.2	abssq() [1/3]	29
	6.1.3.3	abssq() [2/3]	29
	6.1.3.4	abssq() [3/3]	30
	6.1.3.5	adjoint()	30
	6.1.3.6	anticomm()	30
	6.1.3.7	apply() [1/5]	31
	6.1.3.8	apply() [2/5]	31
	6.1.3.9	apply() [3/5]	32
	6.1.3.10	apply() [4/5]	32
	6.1.3.11	apply() [5/5]	33
	6.1.3.12	applyCTRL() [1/2]	33
	6.1.3.13	applyCTRL() [2/2]	34
	6.1.3.14	applyQFT()	35
	6.1.3.15	applyTFQ()	35
	6.1.3.16	avg()	36
	6.1.3.17	bloch2rho()	36
	6.1.3.18	choi2kraus()	37
	6.1.3.19	choi2super()	37
	6.1.3.20	comm()	38
	6.1.3.21	complement()	38
	6.1.3.22	compperm()	38
	6.1.3.23	concurrence()	40
	6.1.3.24	conjugate()	40
	6.1.3.25	contfrac2x()	41
	6.1.3.26	convergents() [1/2]	41

6.1.3.27	convergents() [2/2]	42
6.1.3.28	cor()	42
6.1.3.29	cosm()	43
6.1.3.30	cov()	43
6.1.3.31	cwise()	43
6.1.3.32	det()	44
6.1.3.33	dirsum() [1/4]	44
6.1.3.34	dirsum() [2/4]	45
6.1.3.35	dirsum() [3/4]	45
6.1.3.36	dirsum() [4/4]	46
6.1.3.37	dirsumpow()	46
6.1.3.38	disp() [1/5]	47
6.1.3.39	disp() [2/5]	47
6.1.3.40	disp() [3/5]	47
6.1.3.41	disp() [4/5]	48
6.1.3.42	disp() [5/5]	48
6.1.3.43	egcd()	49
6.1.3.44	eig()	49
6.1.3.45	entanglement() [1/2]	50
6.1.3.46	entanglement() [2/2]	50
6.1.3.47	entropy() [1/2]	51
6.1.3.48	entropy() [2/2]	51
6.1.3.49	evals()	52
6.1.3.50	evects()	52
6.1.3.51	expm()	52
6.1.3.52	factors()	53
6.1.3.53	funm()	53
6.1.3.54	gcd() [1/2]	54
6.1.3.55	gcd() [2/2]	54
6.1.3.56	gconcurrence()	55

iv CONTENTS

6.1.3.57	grams() [1/3]	55
6.1.3.58	grams() [2/3]	55
6.1.3.59	grams() [3/3]	56
6.1.3.60	heig()	56
6.1.3.61	hevals()	57
6.1.3.62	hevects()	57
6.1.3.63	inverse()	58
6.1.3.64	invperm()	58
6.1.3.65	ip() [1/2]	58
6.1.3.66	ip() [2/2]	59
6.1.3.67	isprime()	59
6.1.3.68	kraus2choi()	60
6.1.3.69	kraus2super()	60
6.1.3.70	kron() [1/4]	61
6.1.3.71	kron() [2/4]	61
6.1.3.72	kron() [3/4]	62
6.1.3.73	kron() [4/4]	62
6.1.3.74	kronpow()	62
6.1.3.75	lcm() [1/2]	63
6.1.3.76	lcm() [2/2]	63
6.1.3.77	load()	64
6.1.3.78	loadMATLAB() [1/2]	64
6.1.3.79	loadMATLAB() [2/2]	65
6.1.3.80	logdet()	66
6.1.3.81	logm()	66
6.1.3.82	lognegativity() [1/2]	67
6.1.3.83	lognegativity() [2/2]	67
6.1.3.84	marginalX()	67
6.1.3.85	marginalY()	69
6.1.3.86	measure() [1/9]	69

6.1.3.87 measure() [2/9]	70
6.1.3.88 measure() [3/9]	70
6.1.3.89 measure() [4/9]	70
6.1.3.90 measure() [5/9]	'1
6.1.3.91 measure() [6/9]	2
6.1.3.92 measure() [7/9]	72
6.1.3.93 measure() [8/9]	73
6.1.3.94 measure() [9/9]	74
6.1.3.95 measure_seq() [1/2]	⁷ 4
6.1.3.96 measure_seq() [2/2]	75
6.1.3.97 mket() [1/2]	75
6.1.3.98 mket() [2/2]	76
6.1.3.99 modinv()	76
6.1.3.100 modmul()	7
6.1.3.101 modpow()	7
6.1.3.102 mprj() [1/2]	78
6.1.3.103 mprj() [2/2]	79
6.1.3.104 multiidx2n()	79
6.1.3.105 n2multiidx()	30
6.1.3.106 negativity() [1/2]	30
6.1.3.107 negativity() [2/2]	30
6.1.3.108 norm()	31
6.1.3.109 normalize()	31
6.1.3.110 omega()	32
6.1.3.111 operator""""_i()	32
6.1.3.112 powm()	32
6.1.3.113 prj()	33
6.1.3.114 prod() [1/3]	33
6.1.3.115 prod() [2/3]	34
6.1.3.116 prod() [3/3]	34

vi

6.1.3.117 ptrace() [1/2]
6.1.3.118 ptrace() [2/2]
6.1.3.119 ptrace1() [1/2]
6.1.3.120 ptrace1() [2/2]
6.1.3.121 ptrace2() [1/2]
6.1.3.122 ptrace2() [2/2]
6.1.3.123 ptranspose() [1/2]
6.1.3.124 ptranspose() [2/2]
6.1.3.125 QFT()
6.1.3.126 qmutualinfo() [1/2]
6.1.3.127 qmutualinfo() [2/2]
6.1.3.128 rand() [1/5] 90
6.1.3.129 rand() [2/5] 90
6.1.3.130 rand() [3/5] 91
6.1.3.131 rand() [4/5] 91
6.1.3.132 rand() [5/5]
6.1.3.133 randH()
6.1.3.134 randidx()
6.1.3.135 randket()
6.1.3.136 randkraus()
6.1.3.137 randn() [1/4] 94
6.1.3.138 randn() [2/4] 94
6.1.3.139 randn() [3/4]
6.1.3.140 randn() [4/4]
6.1.3.141 randperm()
6.1.3.142 randprime()
6.1.3.143 randprob()
6.1.3.144 randrho()
6.1.3.145 randU()
6.1.3.146 randV()

CONTENTS vii

6.1.3.147 renyi() [1/2]
6.1.3.148 renyi() [2/2]
6.1.3.149 reshape()
6.1.3.150 rho2bloch()
6.1.3.151 rho2pure()
6.1.3.152 save()
6.1.3.153 saveMATLAB() [1/2]
6.1.3.154 saveMATLAB() [2/2]
6.1.3.155 schatten()
6.1.3.156 schmidtA() [1/2]
6.1.3.157 schmidtA() [2/2]
6.1.3.158 schmidtB() [1/2]
6.1.3.159 schmidtB() [2/2]
6.1.3.160 schmidtcoeffs() [1/2]
6.1.3.161 schmidtcoeffs() [2/2]
6.1.3.162 schmidtprobs() [1/2]
6.1.3.163 schmidtprobs() [2/2]
6.1.3.164 sigma()
6.1.3.165 sinm()
6.1.3.166 spectralpowm()
6.1.3.167 sqrtm()
6.1.3.168 sum() [1/3]
6.1.3.169 sum() [2/3]
6.1.3.170 sum() [3/3]
6.1.3.171 super2choi()
6.1.3.172 svals()
6.1.3.173 svd()
6.1.3.174 svdU()
6.1.3.175 svdV()
6.1.3.176 syspermute() [1/2]

viii CONTENTS

		6.1.3.177	7 syspermute() [2/2]	112
		6.1.3.178	8 TFQ()	112
		6.1.3.179	9 trace()	113
		6.1.3.180	0 transpose()	113
		6.1.3.181	1 tsallis() [1/2]	113
		6.1.3.182	2 tsallis() [2/2]	114
		6.1.3.183	3 uniform()	114
		6.1.3.184	4 var()	115
		6.1.3.185	5 x2contfrac()	115
	6.1.4	Variable	Documentation	116
		6.1.4.1	chop	116
		6.1.4.2	ee	116
		6.1.4.3	eps	116
		6.1.4.4	idx_infty	116
		6.1.4.5	infty	116
		6.1.4.6	maxn	117
		6.1.4.7	pi	117
6.2	qpp::ex	ception N	lamespace Reference	117
	6.2.1	Detailed	Description	118
6.3	qpp::ex	perimenta	al Namespace Reference	119
	6.3.1	Detailed	Description	119
6.4	qpp::in	ternal Nan	mespace Reference	119
	6.4.1	Detailed	Description	120
	6.4.2	Function	Documentation	120
		6.4.2.1	check_cvector()	120
		6.4.2.2	check_dims()	120
		6.4.2.3	check_dims_match_cvect()	121
		6.4.2.4	check_dims_match_mat()	121
		6.4.2.5	check_dims_match_rvect()	121
		6.4.2.6	check_eq_dims()	121

		6.4.2.7	check_matching_sizes()	21
		6.4.2.8	check_no_duplicates()	21
		6.4.2.9	check_nonzero_size()	22
		6.4.2.10	check_perm()	22
		6.4.2.11	check_qubit_cvector()	22
		6.4.2.12	check_qubit_matrix()	22
		6.4.2.13	check_qubit_rvector()	22
		6.4.2.14	check_qubit_vector()	22
		6.4.2.15	check_rvector()	23
		6.4.2.16	check_square_mat()	23
		6.4.2.17	check_subsys_match_dims()	23
		6.4.2.18	check_vector()	23
		6.4.2.19	dirsum2()	23
		6.4.2.20	get_dim_subsys()	23
		6.4.2.21	get_num_subsys()	24
		6.4.2.22	kron2()	24
		6.4.2.23	multiidx2n()	24
		6.4.2.24	n2multiidx()	24
		6.4.2.25	variadic_vector_emplace() [1/2]	24
		6.4.2.26	variadic_vector_emplace() [2/2]	24
6.5	qpp::lit	erals Nam	espace Reference	25
	6.5.1	Function	Documentation	25
		6.5.1.1	operator"""" _bra()	25
		6.5.1.2	operator""""_i()	25
		6.5.1.3	operator"""" _ket()	26
		6.5.1.4	operator"""" _prj()	26

7	Clas	s Docu	mentation	129
	7.1	qpp::Bi	t_circuit Class Reference	129
		7.1.1	Detailed Description	131
		7.1.2	Constructor & Destructor Documentation	131
			7.1.2.1 Bit_circuit()	131
		7.1.3	Member Function Documentation	131
			7.1.3.1 CNOT()	131
			7.1.3.2 Dynamic_bitset()	132
			7.1.3.3 FRED()	132
			7.1.3.4 NOT()	132
			7.1.3.5 reset()	133
			7.1.3.6 SWAP()	133
			7.1.3.7 TOF()	133
			7.1.3.8 X()	134
		7.1.4	Member Data Documentation	134
			7.1.4.1 gate_count	134
	7.2	qpp::C	odes Class Reference	134
		7.2.1	Detailed Description	135
		7.2.2	Member Enumeration Documentation	135
			7.2.2.1 Type	136
		7.2.3	Constructor & Destructor Documentation	136
			7.2.3.1 Codes()	136
			7.2.3.2 ~Codes()	136
		7.2.4	Member Function Documentation	136
			7.2.4.1 codeword()	136
		7.2.5	Friends And Related Function Documentation	137
			7.2.5.1 internal::Singleton < const Codes >	137
	7.3	qpp::ex	cception::CustomException Class Reference	137
		7.3.1	Detailed Description	138
		7.3.2	Constructor & Destructor Documentation	138

CONTENTS xi

		7.3.2.1	CustomException()	. 139
	7.3.3	Member F	Function Documentation	. 139
		7.3.3.1	type_description()	. 139
	7.3.4	Member [Data Documentation	. 139
		7.3.4.1	what	. 139
7.4	qpp::ex	xception::D	imsInvalid Class Reference	. 140
	7.4.1	Detailed [Description	. 141
	7.4.2	Member F	Function Documentation	. 141
		7.4.2.1	Exception()	. 141
		7.4.2.2	type_description()	. 141
7.5	qpp::ex	xception::D	imsMismatchCvector Class Reference	. 142
	7.5.1	Detailed [Description	. 143
	7.5.2	Member F	Function Documentation	. 143
		7.5.2.1	Exception()	. 143
		7.5.2.2	type_description()	. 143
7.6	qpp::ex	xception::D	imsMismatchMatrix Class Reference	. 144
	7.6.1	Detailed [Description	. 145
	7.6.2	Member F	Function Documentation	. 145
		7.6.2.1	Exception()	. 145
		7.6.2.2	type_description()	. 145
7.7	qpp::ex	xception::D	imsMismatchRvector Class Reference	. 146
	7.7.1	Detailed [Description	. 147
	7.7.2	Member F	Function Documentation	. 147
		7.7.2.1	Exception()	. 147
		7.7.2.2	type_description()	. 147
7.8	qpp::ex	xception::D	imsMismatchVector Class Reference	. 148
	7.8.1	Detailed [Description	. 149
	7.8.2	Member F	Function Documentation	. 149
		7.8.2.1	Exception()	. 149
		7.8.2.2	type_description()	. 149

xii CONTENTS

7.9	qpp::ex	cception::DimsNotEqual Class Reference
	7.9.1	Detailed Description
	7.9.2	Member Function Documentation
		7.9.2.1 Exception()
		7.9.2.2 type_description()
7.10	qpp::in	ternal::Display_Impl_ Struct Reference
	7.10.1	Member Function Documentation
		7.10.1.1 display_impl_()
7.11	qpp::ex	cception::Duplicates Class Reference
	7.11.1	Detailed Description
	7.11.2	Member Function Documentation
		7.11.2.1 Exception()
		7.11.2.2 type_description()
7.12	qpp::D	ynamic_bitset Class Reference
	7.12.1	Detailed Description
	7.12.2	Member Typedef Documentation
		7.12.2.1 storage_type
		7.12.2.2 value_type
	7.12.3	Constructor & Destructor Documentation
		7.12.3.1 Dynamic_bitset()
		7.12.3.2 ~Dynamic_bitset()
	7.12.4	Member Function Documentation
		7.12.4.1 all()
		7.12.4.2 any()
		7.12.4.3 count()
		7.12.4.4 data()
		7.12.4.5 display()
		7.12.4.6 flip() [1/2]
		7.12.4.7 flip() [2/2]
		7.12.4.8 get()

CONTENTS xiii

		7.12.4.9 index_()	60
		7.12.4.10 none()	61
		7.12.4.11 offset_()	61
		7.12.4.12 operator"!=()	61
		7.12.4.13 operator-()	62
		7.12.4.14 operator==()	62
		7.12.4.15 rand() [1/2]	62
		7.12.4.16 rand() [2/2]	63
		7.12.4.17 reset() [1/2]	63
		7.12.4.18 reset() [2/2]	63
		7.12.4.19 set() [1/2]	64
		7.12.4.20 set() [2/2]	64
		7.12.4.21 size()	64
		7.12.4.22 storage_size()	64
		7.12.4.23 to_string()	65
	7.12.5	Member Data Documentation	65
		7.12.5.1 N	65
		7.12.5.2 storage_size	65
		7.12.5.3 v	66
7.13	qpp::ex	cception::Exception Class Reference	66
	7.13.1	Detailed Description	68
	7.13.2	Constructor & Destructor Documentation	69
		7.13.2.1 Exception()	69
	7.13.3	Member Function Documentation	69
		7.13.3.1 type_description()	69
		7.13.3.2 what()	70
	7.13.4	Member Data Documentation	70
		7.13.4.1 msg	70
		7.13.4.2 where	70
7.14	qpp::Bi	it_circuit::Gate_count Struct Reference	70

xiv CONTENTS

	7.14.1	Member Data Documentation
		7.14.1.1 CNOT
		7.14.1.2 FRED
		7.14.1.3 NOT
		7.14.1.4 SWAP
		7.14.1.5 TOF
		7.14.1.6 X
7.15	qpp::Ga	ates Class Reference
	7.15.1	Detailed Description
	7.15.2	Constructor & Destructor Documentation
		7.15.2.1 Gates()
		7.15.2.2 ~Gates()
	7.15.3	Member Function Documentation
		7.15.3.1 CTRL()
		7.15.3.2 expandout() [1/3]
		7.15.3.3 expandout() [2/3]
		7.15.3.4 expandout() [3/3]
		7.15.3.5 Fd()
		7.15.3.6 get_name()
		7.15.3.7 ld()
		7.15.3.8 MODMUL()
		7.15.3.9 Rn()
		7.15.3.10 RX()
		7.15.3.11 RY()
		7.15.3.12 RZ()
		7.15.3.13 SWAPd()
		7.15.3.14 Xd()
		7.15.3.15 Zd()
	7.15.4	Friends And Related Function Documentation
		7.15.4.1 internal::Singleton < const Gates >

CONTENTS xv

7	'.15.5	Member Data Documentation
		7.15.5.1 CNOT
		7.15.5.2 CNOTba
		7.15.5.3 CZ
		7.15.5.4 FRED
		7.15.5.5 H
		7.15.5.6 ld2
		7.15.5.7 S
		7.15.5.8 SWAP
		7.15.5.9 T
		7.15.5.10 TOF
		7.15.5.11 X
		7.15.5.12 Y
		7.15.5.13 Z
7.16 q	pp::Q0	Circuit::GateStep Struct Reference
7	'.16.1	Detailed Description
7	7.16.2	Constructor & Destructor Documentation
		7.16.2.1 GateStep() [1/2]
		7.16.2.2 GateStep() [2/2]
7	7.16.3	Member Data Documentation
		7.16.3.1 ctrl
		7.16.3.2 gate
		7.16.3.3 gate_type
		7.16.3.4 name
		7.16.3.5 target
7.17 q	pp::ID	isplay Class Reference
7	7.17.1	Detailed Description
7	7.17.2	Constructor & Destructor Documentation
		7.17.2.1 IDisplay() [1/3]
		7.17.2.2 IDisplay() [2/3]

xvi CONTENTS

		7.17.2.3 IDisplay() [3/3]
		7.17.2.4 ~IDisplay()
	7.17.3	Member Function Documentation
		7.17.3.1 display()
		7.17.3.2 operator=() [1/2]
		7.17.3.3 operator=() [2/2]
	7.17.4	Friends And Related Function Documentation
		7.17.4.1 operator<<
7.18	qpp::lJ	SON Class Reference
	7.18.1	Detailed Description
	7.18.2	Constructor & Destructor Documentation
		7.18.2.1 IJSON() [1/3]
		7.18.2.2 IJSON() [2/3]
		7.18.2.3 IJSON() [3/3]
		7.18.2.4 ~IJSON()
	7.18.3	Member Function Documentation
		7.18.3.1 operator=() [1/2]
		7.18.3.2 operator=() [2/2]
		7.18.3.3 to_JSON()
7.19	qpp::ln	it Class Reference
	7.19.1	Detailed Description
	7.19.2	Constructor & Destructor Documentation
		7.19.2.1 Init()
		7.19.2.2 ~Init()
	7.19.3	Friends And Related Function Documentation
		7.19.3.1 internal::Singleton < const Init >
7.20	qpp::ex	cception::InvalidIterator Class Reference
	7.20.1	Detailed Description
	7.20.2	Member Function Documentation
		7.20.2.1 Exception()

CONTENTS xvii

		7.20.2.2 type_description()	197
7.21	qpp::int	ternal::IOManipEigen Class Reference	197
	7.21.1	Constructor & Destructor Documentation	199
		7.21.1.1 IOManipEigen() [1/2]	199
		7.21.1.2 IOManipEigen() [2/2]	199
	7.21.2	Member Function Documentation	199
		7.21.2.1 display()	199
	7.21.3	Member Data Documentation	199
		7.21.3.1 A	199
		7.21.3.2 chop	200
7.22	qpp::int	ternal::IOManipPointer< PointerType > Class Template Reference	200
	7.22.1	Constructor & Destructor Documentation	201
		7.22.1.1 IOManipPointer() [1/2]	201
		7.22.1.2 IOManipPointer() [2/2]	201
	7.22.2	Member Function Documentation	201
		7.22.2.1 display()	202
		7.22.2.2 operator=()	202
	7.22.3	Member Data Documentation	202
		7.22.3.1 end	202
		7.22.3.2 N	202
		7.22.3.3 p	202
		7.22.3.4 separator	203
		7.22.3.5 start	203
7.23	qpp::int	ternal::IOManipRange < InputIterator > Class Template Reference	203
	7.23.1	Constructor & Destructor Documentation	204
		7.23.1.1 IOManipRange() [1/2]	205
		7.23.1.2 IOManipRange() [2/2]	205
	7.23.2	Member Function Documentation	205
		7.23.2.1 display()	205
		7.23.2.2 operator=()	205

xviii CONTENTS

	7.23.3	Member Data Documentation	05
		7.23.3.1 end	06
		7.23.3.2 first	06
		7.23.3.3 last	06
		7.23.3.4 separator	06
		7.23.3.5 start	06
7.24	qpp::is_	_complex< T > Struct Template Reference	07
	7.24.1	Detailed Description	07
7.25	qpp::is_	_complex< std::complex< T > > Struct Template Reference	80
	7.25.1	Detailed Description	80
7.26	qpp::is_	_iterable< T, typename > Struct Template Reference	09
	7.26.1	Detailed Description	09
7.27		_iterable $<$ T, to_void $<$ decltype(std::declval $<$ T $>$ ().begin()), decltype(std::declval $<$ T d()), decltype(*(std::declval $<$ T $>$ ().begin())) $>$ Struct Template Reference 2	10
	7.27.1	Detailed Description	11
7.28	qpp::is_	_matrix_expression< Derived > Struct Template Reference	11
	7.28.1	Detailed Description	11
7.29	qpp::Q	Circuit::iterator Class Reference	12
	7.29.1	Detailed Description	13
	7.29.2	Member Typedef Documentation	13
		7.29.2.1 difference_type	13
		7.29.2.2 iterator_category	13
		7.29.2.3 pointer	13
		7.29.2.4 reference	14
		7.29.2.5 value_type	14
	7.29.3	Constructor & Destructor Documentation	14
		7.29.3.1 iterator() [1/2]	14
		7.29.3.2 iterator() [2/2]	14
	7.29.4	Member Function Documentation	14
		7.29.4.1 operator"!=()	14
		7.29.4.2 operator*()	15

CONTENTS xix

		7.29.4.3 operator++() [1/2]	15
		7.29.4.4 operator++() [2/2]	15
		7.29.4.5 operator=()	16
		7.29.4.6 operator==()	16
		7.29.4.7 set_begin_()	16
		7.29.4.8 set_end_()	16
	7.29.5	Member Data Documentation	17
		7.29.5.1 elem	17
		7.29.5.2 qcd	17
7.30	qpp::ma	ake_void< Ts > Struct Template Reference	17
	7.30.1	Detailed Description	17
	7.30.2	Member Typedef Documentation	18
		7.30.2.1 type	18
7.31	qpp::ex	cception::MatrixMismatchSubsys Class Reference	18
	7.31.1	Detailed Description	19
	7.31.2	Member Function Documentation	19
		7.31.2.1 Exception()	19
		7.31.2.2 type_description()	20
7.32	qpp::ex	cception::MatrixNotCvector Class Reference	20
	7.32.1	Detailed Description	21
	7.32.2	Member Function Documentation	21
		7.32.2.1 Exception()	21
		7.32.2.2 type_description()	22
7.33	qpp::ex	cception::MatrixNotRvector Class Reference	22
	7.33.1	Detailed Description	23
	7.33.2	Member Function Documentation	23
		7.33.2.1 Exception()	23
		7.33.2.2 type_description()	24
7.34	qpp::ex	cception::MatrixNotSquare Class Reference	24
	7.34.1	Detailed Description	25

	7.34.2	Member Function Documentation	225
		7.34.2.1 Exception()	225
		7.34.2.2 type_description()	226
7.35	qpp::ex	xception::MatrixNotSquareNorCvector Class Reference	226
	7.35.1	Detailed Description	227
	7.35.2	Member Function Documentation	227
		7.35.2.1 Exception()	227
		7.35.2.2 type_description()	228
7.36	qpp::ex	xception::MatrixNotSquareNorRvector Class Reference	228
	7.36.1	Detailed Description	229
	7.36.2	Member Function Documentation	229
		7.36.2.1 Exception()	229
		7.36.2.2 type_description()	230
7.37	qpp::ex	cception::MatrixNotSquareNorVector Class Reference	230
	7.37.1	Detailed Description	231
	7.37.2	Member Function Documentation	231
		7.37.2.1 Exception()	231
		7.37.2.2 type_description()	232
7.38	qpp::ex	cception::MatrixNotVector Class Reference	232
	7.38.1	Detailed Description	233
	7.38.2	Member Function Documentation	233
		7.38.2.1 Exception()	233
		7.38.2.2 type_description()	234
7.39	qpp::Q	Circuit::MeasureStep Struct Reference	234
	7.39.1	Detailed Description	235
	7.39.2	Constructor & Destructor Documentation	235
		7.39.2.1 MeasureStep() [1/2]	235
		7.39.2.2 MeasureStep() [2/2]	235
	7.39.3	Member Data Documentation	236
		7.39.3.1 c_reg	236

CONTENTS xxi

		7.39.3.2 mats	23
		7.39.3.3 measurement_type	23
		7.39.3.4 name	23
		7.39.3.5 target	23
7.40	qpp::ex	ception::NoCodeword Class Reference	23
	7.40.1	Detailed Description	23
	7.40.2	Member Function Documentation	23
		7.40.2.1 Exception()	23
		7.40.2.2 type_description()	23
7.41	qpp::No	iseBase< T > Class Template Reference	23
	7.41.1	Detailed Description	24
	7.41.2	Member Typedef Documentation	24
		7.41.2.1 noise_type	24
	7.41.3	Constructor & Destructor Documentation	24
		7.41.3.1 NoiseBase() [1/2]	24
		7.41.3.2 NoiseBase() [2/2]	24
		7.41.3.3 ~NoiseBase()	24
	7.41.4	Member Function Documentation	24
		7.41.4.1 compute_probs_()	24
		7.41.4.2 compute_state_()	24
		7.41.4.3 get_d()	24
		7.41.4.4 get_Ks()	24
		7.41.4.5 get_last_idx()	24
		7.41.4.6 get_last_K()	24
		7.41.4.7 get_last_p()	24
		7.41.4.8 get_probs()	24
		7.41.4.9 operator()() [1/2]	24
		7.41.4.10 operator()() [2/2]	24
	7.41.5	Member Data Documentation	24
		7.41.5.1 d	24

xxii CONTENTS

		7.41.5.2	ge	enerate	ed					 	 	 	 	 	 	 245
		7.41.5.3	i_							 	 	 	 	 	 	 246
		7.41.5.4	K	s						 	 	 	 	 	 	 246
		7.41.5.5	pr	obs_						 	 	 	 	 	 	 246
7.42	qpp::No	oiseType C	Clas	ss Refe	erenc	ce .				 	 	 	 	 	 	 246
	7.42.1	Detailed I	De	scriptio	on .					 	 	 	 	 	 	 246
7.43	qpp::ex	ception::N	VotE	3ipartit	te Cla	ass F	Refere	ence		 	 	 	 	 	 	 247
	7.43.1	Detailed I	De	scriptio	on .					 	 	 	 	 	 	 248
	7.43.2	Member I	Fur	nction	Docu	umer	ntation	n .		 	 	 	 	 	 	 248
		7.43.2.1	E	xceptio	on() .					 	 	 	 	 	 	 248
		7.43.2.2	ty	pe_de	scrip	otion(()			 	 	 	 	 	 	 248
7.44	qpp::ex	ception::N	Votl	mplem	nente	ed Cla	ass P	Refere	ence	 	 	 	 	 	 	 249
	7.44.1	Detailed I	De	scriptio	on .					 	 	 	 	 	 	 250
	7.44.2	Member I	Fur	nction	Docu	umer	ntation	n .		 	 	 	 	 	 	 250
		7.44.2.1	E	xceptio	on() .					 	 	 	 	 	 	 250
		7.44.2.2	ty	pe_de	scrip	otion(()			 	 	 	 	 	 	 250
7.45	qpp::ex	ception::N	Vot(QubitC	vecto	or Cl	ass F	Refere	ence	 	 	 	 	 	 	 251
	7.45.1	Detailed I	De	scriptio	on .					 	 	 	 	 	 	 252
	7.45.2	Member I	Fur	nction	Docu	umer	ntation	n .		 	 	 	 	 	 	 252
		7.45.2.1	E	xceptio	on() .					 	 	 	 	 	 	 252
		7.45.2.2	ty	pe_de	scrip	otion(()			 	 	 	 	 	 	 252
7.46	qpp::ex	ception::N	Vot(QubitM	1atrix	Clas	ss Re	eferer	nce .	 	 	 	 	 	 	 253
	7.46.1	Detailed I	De	scriptio	on .					 	 	 	 	 	 	 254
	7.46.2	Member I	Fur	nction	Docu	umer	ntatio	n .		 	 	 	 	 	 	 254
		7.46.2.1	E	xceptio	on() .					 	 	 	 	 	 	 254
		7.46.2.2	ty	pe_de	scrip	otion(()			 	 	 	 	 	 	 254
7.47	qpp::ex	ception::N	Vot(QubitR	lvecto	or Cl	ass F	Refere	ence	 	 	 	 	 	 	 255
	7.47.1	Detailed I	De	scriptio	on .					 	 	 	 	 	 	 256
	7.47.2	Member I	Fur	nction	Docu	umer	ntatio	n .		 	 	 	 	 	 	 256
		7.47.2.1	E	xceptic	on() .					 	 	 	 	 	 	 256

CONTENTS xxiii

		7.47.2.2	type_description()	 	 	 	 	256
7.48	qpp::ex	ception::N	tQubitSubsys Class Reference	 	 	 	 	257
	7.48.1	Detailed [escription	 	 	 	 	258
	7.48.2	Member F	unction Documentation	 	 	 	 	258
		7.48.2.1	Exception()	 	 	 	 	258
		7.48.2.2	type_description()	 	 	 	 	258
7.49	qpp::ex	ception::N	tQubitVector Class Reference	 	 	 	 	259
	7.49.1	Detailed [escription	 	 	 	 	260
	7.49.2	Member F	unction Documentation	 	 	 	 	260
		7.49.2.1	Exception()	 	 	 	 	260
		7.49.2.2	type_description()	 	 	 	 	260
7.50	qpp::ex	ception::O	utOfRange Class Reference	 	 	 	 	261
	7.50.1	Detailed [escription	 	 	 	 	262
	7.50.2	Member F	unction Documentation	 	 	 	 	262
		7.50.2.1	Exception()	 	 	 	 	262
		7.50.2.2	type_description()	 	 	 	 	262
7.51	qpp::ex	ception::Po	rmInvalid Class Reference	 	 	 	 	263
	7.51.1	Detailed [escription	 	 	 	 	264
	7.51.2	Member F	unction Documentation	 	 	 	 	264
		7.51.2.1	Exception()	 	 	 	 	264
		7.51.2.2	type_description()	 	 	 	 	264
7.52	qpp::ex	ception::Pe	rmMismatchDims Class Reference	 	 	 	 	265
	7.52.1	Detailed [escription	 	 	 	 	266
	7.52.2	Member F	unction Documentation	 	 	 	 	266
		7.52.2.1	Exception()	 	 	 	 	266
		7.52.2.2	type_description()	 	 	 	 	266
7.53	qpp::Q	Circuit Clas	s Reference	 	 	 	 	267
	7.53.1	Detailed [escription	 	 	 	 	271
	7.53.2	Member 7	pedef Documentation	 	 	 	 	271
		7.53.2.1	const_iterator	 	 	 	 	271

xxiv CONTENTS

7.53.3	Member Enumeration Documentation	271
	7.53.3.1 GateType	271
	7.53.3.2 MeasureType	272
	7.53.3.3 StepType	272
7.53.4	Constructor & Destructor Documentation	272
	7.53.4.1 QCircuit()	272
	7.53.4.2 ~QCircuit()	273
7.53.5	Member Function Documentation	273
	7.53.5.1 begin() [1/2]	273
	7.53.5.2 begin() [2/2]	273
	7.53.5.3 cbegin()	274
	7.53.5.4 cCTRL() [1/4]	274
	7.53.5.5 cCTRL() [2/4]	274
	7.53.5.6 cCTRL() [3/4]	275
	7.53.5.7 cCTRL() [4/4]	275
	7.53.5.8 cCTRL_custom()	276
	7.53.5.9 cend()	276
	7.53.5.10 CTRL() [1/4]	276
	7.53.5.11 CTRL() [2/4]	277
	7.53.5.12 CTRL() [3/4]	277
	7.53.5.13 CTRL() [4/4]	278
	7.53.5.14 CTRL_custom()	278
	7.53.5.15 display()	279
	7.53.5.16 end() [1/2]	279
	7.53.5.17 end() [2/2]	280
	7.53.5.18 gate() [1/3]	280
	7.53.5.19 gate() [2/3]	280
	7.53.5.20 gate() [3/3]	281
	7.53.5.21 gate_custom()	281
	7.53.5.22 gate_fan() [1/3]	282

CONTENTS xxv

	7.53.5.23 gate_fan() [2/3]	282
	7.53.5.24 gate_fan() [3/3]	282
	7.53.5.25 get_d()	283
	7.53.5.26 get_gate_count()	283
	7.53.5.27 get_gates()	283
	7.53.5.28 get_measured() [1/2]	283
	7.53.5.29 get_measured() [2/2]	284
	7.53.5.30 get_measurement_count()	284
	7.53.5.31 get_measurements()	284
	7.53.5.32 get_name()	285
	7.53.5.33 get_nc()	285
	7.53.5.34 get_non_measured()	285
	7.53.5.35 get_nq()	285
	7.53.5.36 get_step_count()	286
	7.53.5.37 measureV() [1/2]	286
	7.53.5.38 measureV() [2/2]	286
	7.53.5.39 measureZ()	287
	7.53.5.40 QFT()	287
	7.53.5.41 TFQ()	287
	7.53.5.42 to_JSON()	288
7.53.6	Friends And Related Function Documentation	288
	7.53.6.1 operator<< [1/4]	288
	7.53.6.2 operator<< [2/4]	289
	7.53.6.3 operator<< [3/4]	289
	7.53.6.4 operator<< [4/4]	289
7.53.7	Member Data Documentation	290
	7.53.7.1 d	290
	7.53.7.2 gates	290
	7.53.7.3 measured	290
	7.53.7.4 measurements	290

xxvi CONTENTS

	7.53.7.5 name
	7.53.7.6 nc
	7.53.7.7 nq
	7.53.7.8 step_types
7.54 qpp::C	Engine Class Reference
7.54.1	Detailed Description
7.54.2	Constructor & Destructor Documentation
	7.54.2.1 QEngine() [1/2]
	7.54.2.2 QEngine() [2/2]
	7.54.2.3 ~QEngine()
7.54.3	Member Function Documentation
	7.54.3.1 display()
	7.54.3.2 execute() [1/2]
	7.54.3.3 execute() [2/2]
	7.54.3.4 get_circuit()
	7.54.3.5 get_dit()
	7.54.3.6 get_dits()
	7.54.3.7 get_measured() [1/2]
	7.54.3.8 get_measured() [2/2]
	7.54.3.9 get_not_measured()
	7.54.3.10 get_probs()
	7.54.3.11 get_psi()
	7.54.3.12 get_ref_psi()
	7.54.3.13 get_relative_pos_()
	7.54.3.14 reset()
	7.54.3.15 set_dit()
	7.54.3.16 set_measured_()
	7.54.3.17 to_JSON()
7.54.4	Member Data Documentation
	7.54.4.1 dits

CONTENTS xxvii

		7.54.4.2 probs	300
		7.54.4.3 psi	300
		7.54.4.4 qcd	300
		7.54.4.5 subsys	300
7.55	qpp::Q	ubitAmplitudeDampingNoise Class Reference	301
	7.55.1	Detailed Description	302
	7.55.2	Constructor & Destructor Documentation	302
		7.55.2.1 QubitAmplitudeDampingNoise()	302
7.56	qpp::Q	ubitBitFlipNoise Class Reference	302
	7.56.1	Detailed Description	303
	7.56.2	Constructor & Destructor Documentation	303
		7.56.2.1 QubitBitFlipNoise()	303
7.57	qpp::Q	ubitBitPhaseFlipNoise Class Reference	304
	7.57.1	Detailed Description	305
	7.57.2	Constructor & Destructor Documentation	305
		7.57.2.1 QubitBitPhaseFlipNoise()	305
7.58	qpp::Q	ubitDepolarizingNoise Class Reference	305
	7.58.1	Detailed Description	306
	7.58.2	Constructor & Destructor Documentation	306
		7.58.2.1 QubitDepolarizingNoise()	306
7.59	qpp::Q	ubitPhaseDampingNoise Class Reference	307
	7.59.1	Detailed Description	308
	7.59.2	Constructor & Destructor Documentation	308
		7.59.2.1 QubitPhaseDampingNoise()	308
7.60	qpp::Q	ubitPhaseFlipNoise Class Reference	308
	7.60.1	Detailed Description	309
	7.60.2	Constructor & Destructor Documentation	309
		7.60.2.1 QubitPhaseFlipNoise()	309
7.61	qpp::ex	ception::QuditAlreadyMeasured Class Reference	310
	7.61.1	Detailed Description	311

xxviii CONTENTS

	7.61.2	Member Function Documentation	11
		7.61.2.1 Exception()	11
		7.61.2.2 type_description()	12
7.62	qpp::Qı	uditDepolarizingNoise Class Reference	12
	7.62.1	Detailed Description	13
	7.62.2	Constructor & Destructor Documentation	13
		7.62.2.1 QuditDepolarizingNoise()	13
	7.62.3	Member Function Documentation	14
		7.62.3.1 fill_Ks_()	14
		7.62.3.2 fill_probs_()	14
7.63	qpp::Ra	andomDevices Class Reference	15
	7.63.1	Detailed Description	16
	7.63.2	Constructor & Destructor Documentation	16
		7.63.2.1 RandomDevices()	16
		7.63.2.2 ~RandomDevices()	17
	7.63.3	Member Function Documentation	17
		7.63.3.1 get_prng()	17
		7.63.3.2 load()	17
		7.63.3.3 save()	17
	7.63.4	Friends And Related Function Documentation	18
		7.63.4.1 internal::Singleton < RandomDevices >	18
	7.63.5	Member Data Documentation	18
		7.63.5.1 prng	18
		7.63.5.2 rd	18
7.64	qpp::int	ternal::Singleton < T > Class Template Reference	18
	7.64.1	Detailed Description	19
	7.64.2	Constructor & Destructor Documentation	19
		7.64.2.1 Singleton() [1/2]	20
		7.64.2.2 Singleton() [2/2]	20
		7.64.2.3 ~Singleton()	20

CONTENTS xxix

	7.64.3	Member Function Documentation
		7.64.3.1 get_instance()
		7.64.3.2 get_thread_local_instance()
		7.64.3.3 operator=()
7.65	qpp::ex	cception::SizeMismatch Class Reference
	7.65.1	Detailed Description
	7.65.2	Member Function Documentation
		7.65.2.1 Exception()
		7.65.2.2 type_description()
7.66	qpp::No	oiseType::StateDependent Class Reference
	7.66.1	Detailed Description
7.67	qpp::No	oiseType::StateIndependent Class Reference
	7.67.1	Detailed Description
7.68	qpp::St	tates Class Reference
	7.68.1	Detailed Description
	7.68.2	Constructor & Destructor Documentation
		7.68.2.1 States()
		7.68.2.2 ~States()
	7.68.3	Member Function Documentation
		7.68.3.1 jn()
		7.68.3.2 mes()
		7.68.3.3 minus()
		7.68.3.4 one()
		7.68.3.5 plus()
		7.68.3.6 zero()
	7.68.4	Friends And Related Function Documentation
		7.68.4.1 internal::Singleton < const States >
	7.68.5	Member Data Documentation
		7.68.5.1 b00
		7.68.5.2 b01

		7.68.5.3 b10	29
		7.68.5.4 b11	29
		7.68.5.5 GHZ	29
		7.68.5.6 pb00	29
		7.68.5.7 pb01	30
		7.68.5.8 pb10	30
		7.68.5.9 pb11	30
		7.68.5.10 pGHZ	30
		7.68.5.11 pW	30
		7.68.5.12 px0	30
		7.68.5.13 px1	31
		7.68.5.14 py0	31
		7.68.5.15 py1	31
		7.68.5.16 pz0	31
		7.68.5.17 pz1	31
		7.68.5.18 W	31
		7.68.5.19 x0	32
		7.68.5.20 x1	32
		7.68.5.21 y0	32
		7.68.5.22 y1	32
		7.68.5.23 z0	32
		7.68.5.24 z1	32
7.69	qpp::ex	cception::SubsysMismatchDims Class Reference	33
	7.69.1	Detailed Description	34
	7.69.2	Member Function Documentation	34
		7.69.2.1 Exception()	34
		7.69.2.2 type_description()	34
7.70	qpp::Tii	mer < T, CLOCK_T > Class Template Reference	35
	7.70.1	Detailed Description	36
	7.70.2	Constructor & Destructor Documentation	36

CONTENTS xxxi

		7.70.2.1 Timer() [1/3]	36
		7.70.2.2 Timer() [2/3]	37
		7.70.2.3 Timer() [3/3]	37
		7.70.2.4 ~Timer()	37
	7.70.3	Member Function Documentation	37
		7.70.3.1 display()	37
		7.70.3.2 get_duration()	38
		7.70.3.3 operator=() [1/2]	38
		7.70.3.4 operator=() [2/2]	38
		7.70.3.5 tic()	39
		7.70.3.6 tics()	39
		7.70.3.7 toc()	39
	7.70.4	Member Data Documentation	39
		7.70.4.1 end	39
		7.70.4.2 start	40
7.71	qpp::ex	cception::TypeMismatch Class Reference	40
	7.71.1	Detailed Description	41
	7.71.2	Member Function Documentation	41
		7.71.2.1 Exception()	41
		7.71.2.2 type_description()	42
7.72	qpp::ex	cception::UndefinedType Class Reference	42
	7.72.1	Detailed Description	43
	7.72.2	Member Function Documentation	43
		7.72.2.1 Exception()	43
		7.72.2.2 type_description()	44
7.73	qpp::ex	cception::Unknown Class Reference	44
	7.73.1	Detailed Description	45
	7.73.2	Member Function Documentation	45
		7.73.2.1 Exception()	45
		7.73.2.2 type_description()	46

xxxii CONTENTS

	7.74	qpp::Q	Circuit::iterator::value_type_ Struct Reference	l 6
		7.74.1	Constructor & Destructor Documentation	1 7
			7.74.1.1 value_type_() [1/2]	1 7
			7.74.1.2 value_type_() [2/2]	ŀ 7
		7.74.2	Member Function Documentation	18
			7.74.2.1 display()	18
			7.74.2.2 operator=()	18
		7.74.3	Member Data Documentation	18
			7.74.3.1 gates_ip	18
			7.74.3.2 ip	19
			7.74.3.3 measurements_ip	19
			7.74.3.4 type	19
			7.74.3.5 value_type_qcd	19
	7.75	qpp::ex	cception::ZeroSize Class Reference	50
		7.75.1	Detailed Description	51
		7.75.2	Member Function Documentation	51
			7.75.2.1 Exception()	51
			7.75.2.2 type_description()	51
8	File I	Docume	entation 35	53
	8.1	classes	s/circuits.h File Reference	53
		8.1.1	Detailed Description	54
	8.2	classes	s/codes.h File Reference	54
		8.2.1	Detailed Description	54
	8.3	classes	s/exception.h File Reference	55
		8.3.1	Detailed Description	57
	8.4	classes	s/gates.h File Reference	57
		8.4.1	Detailed Description	57
	8.5	classes	s/idisplay.h File Reference	58
		8.5.1	Detailed Description	58
	8.6	classes	s/init.h File Reference	58

CONTENTS xxxiii

	8.6.1	Detailed Description		 	 	 	 	359
8.7	classes	/noise.h File Reference		 	 	 	 	359
	8.7.1	Detailed Description		 	 	 	 	360
8.8	classes	/random_devices.h File	Reference	 	 	 	 	360
	8.8.1	Detailed Description		 	 	 	 	360
8.9	classes	/reversible.h File Refer	ence	 	 	 	 	361
	8.9.1	Detailed Description		 	 	 	 	361
8.10	classes	states.h File Referenc	e	 	 	 	 	361
	8.10.1	Detailed Description		 	 	 	 	362
8.11	classes	/timer.h File Reference		 	 	 	 	362
	8.11.1	Detailed Description		 	 	 	 	363
8.12	constar	nts.h File Reference .		 	 	 	 	363
	8.12.1	Detailed Description		 	 	 	 	364
8.13	entang	ement.h File Reference		 	 	 	 	364
	8.13.1	Detailed Description		 	 	 	 	366
8.14	entropi	es.h File Reference .		 	 	 	 	366
	8.14.1	Detailed Description		 	 	 	 	367
8.15	experin	nental/experimental.h F	ile Reference	 	 	 	 	367
	8.15.1	Detailed Description		 	 	 	 	367
8.16	function	ns.h File Reference		 	 	 	 	367
	8.16.1	Detailed Description		 	 	 	 	372
8.17	input_c	utput.h File Reference		 	 	 	 	372
	8.17.1	Detailed Description		 	 	 	 	373
8.18	instrum	ents.h File Reference		 	 	 	 	373
	8.18.1	Detailed Description		 	 	 	 	374
8.19	interna	/classes/iomanip.h File	Reference .	 	 	 	 	374
	8.19.1	Detailed Description		 	 	 	 	375
8.20	interna	/classes/singleton.h Fil	e Reference	 	 	 	 	375
	8.20.1	Detailed Description		 	 	 	 	376
8.21	interna	/util.h File Reference .		 	 	 	 	376

	8.21.1 Detailed Description	377
8.22	MATLAB/matlab.h File Reference	378
	8.22.1 Detailed Description	378
8.23	number_theory.h File Reference	378
	8.23.1 Detailed Description	380
8.24	operations.h File Reference	380
	8.24.1 Detailed Description	382
8.25	qpp.h File Reference	382
	8.25.1 Detailed Description	384
	8.25.2 Macro Definition Documentation	384
	8.25.2.1 QPP_UNUSED	384
8.26	random.h File Reference	384
	8.26.1 Detailed Description	385
8.27	statistics.h File Reference	386
	8.27.1 Detailed Description	387
8.28	traits.h File Reference	387
	8.28.1 Detailed Description	388
8.29	types.h File Reference	388
	8.29.1 Detailed Description	389
8.30	/Users/vlad/qpp/README.md File Reference	389
Index		391

Chapter 1

Quantum++

Version 1.1 - 26 November 2018

Build status:

Chat (questions/issues)

About

Quantum++ is a modern C++11 general purpose quantum computing library, composed solely of template header files. Quantum++ is written in standard C++11 and has very low external dependencies, using only the Eigen 3 linear algebra header-only template library and, if available, the OpenMP multi-processing library.

Quantum++ is not restricted to qubit systems or specific quantum information processing tasks, being capable of simulating arbitrary quantum processes. The main design factors taken in consideration were the ease of use, high portability, and high performance. The library's simulation capabilities are only restricted by the amount of available physical memory. On a typical machine (Intel i5 8Gb RAM) Quantum++ can successfully simulate the evolution of 25 qubits in a pure state or of 12 qubits in a mixed state reasonably fast.

To report any bugs or ask for additional features/enhancements, please submit an issue with an appropriate label.

If you are interesting in contributing to this project, feel free to contact me. Alternatively, create a custom branch, add your contribution, then finally create a pull request. If I accept the pull request, I will merge your custom branch with the latest development branch. The latter will eventually be merged into a future release version. To contribute, you need to have a solid knowledge of C++ (preferably C++11), including templates and the standard library, a basic knowledge of quantum computing and linear algebra, and working experience with Eigen 3.

For additional Eigen 3 documentation see http://eigen.tuxfamily.org/dox/. For a simple Eigen 3 quick ASCII reference see http://eigen.tuxfamily.org/dox/AsciiQuickReference.txt.

Copyright (c) 2013 - 2019 Vlad Gheorghiu, vgheorgh AT gmail DOT com.

License

Quantum++ is distributed under the MIT license. Please see the LICENSE file for more details.

Installation instructions and further documentation

Please see the installation guide https://github.com/vsoftco/qpp/blob/master/INSTALL.md "`INSTALL.md`" and the comprehensive Wiki for further documentation and detailed examples.

The official API documentation is available in PDF and HTML formats in the doc folder.

2 Quantum++

Chapter 2

Namespace Index

2.1 Namespace List

Here is a list of all namespaces with brief descriptions:

qpp
Quantum++ main namespace
qpp::exception
Quantum++ exception hierarchy namespace
qpp::experimental
Experimental/test functions/classes, do not use or modify
qpp::internal
Internal utility functions, do not use them directly or modify them
qpp::literals

4 Namespace Index

Chapter 3

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

qpp::internal::Display_Impl
qpp::internal::IOManipEigen
std::exception
qpp::exception::Exception
qpp::exception::CustomException
qpp::exception::DimsInvalid
qpp::exception::DimsMismatchCvector
qpp::exception::DimsMismatchMatrix
qpp::exception::DimsMismatchRvector
qpp::exception::DimsMismatchVector
qpp::exception::DimsNotEqual
qpp::exception::Duplicates
qpp::exception::InvalidIterator
qpp::exception::MatrixMismatchSubsys
qpp::exception::MatrixNotCvector
qpp::exception::MatrixNotRvector
qpp::exception::MatrixNotSquare
qpp::exception::MatrixNotSquareNorCvector
qpp::exception::MatrixNotSquareNorRvector
qpp::exception::MatrixNotSquareNorVector
qpp::exception::MatrixNotVector
qpp::exception::NoCodeword
qpp::exception::NotBipartite
qpp::exception::NotImplemented
qpp::exception::NotQubitCvector
qpp::exception::NotQubitMatrix
qpp::exception::NotQubitRvector
qpp::exception::NotQubitSubsys
qpp::exception::NotQubitVector
qpp::exception::OutOfRange
qpp::exception::PermInvalid
qpp::exception::PermMismatchDims
qpp::exception::QuditAlreadyMeasured
qpp::exception::SizeMismatch
qpp::exception::SubsysMismatchDims

6 Hierarchical Index

qpp::exception::TypeMismatch	
qpp::exception::UndefinedType	
qpp::exception::Unknown	
qpp::exception::ZeroSize	50
false_type	
qpp::is_complex < T >	
qpp::is_iterable < T, typename >	
qpp::Bit_circuit::Gate_count	
qpp::QCircuit::GateStep	
qpp::IDisplay	
qpp::Dynamic_bitset	
qpp::Bit_circuit	
qpp::internal::IOManipEigen	
qpp::internal::IOManipPointer< PointerType >	
qpp::internal::IOManipRange< InputIterator >	
qpp::QCircuit	
qpp::QCircuit::iterator::value_type	
qpp::QEngine	
qpp::Timer < T, CLOCK_T >	
qpp::IJSON	
qpp::QCircuit	
qpp::QEngine	92
is_base_of	
qpp::is_matrix_expression< Derived >	
qpp::QCircuit::iterator	
qpp::make_void < Ts >	
qpp::QCircuit::MeasureStep	
qpp::NoiseBase < T >	
qpp::NoiseBase < NoiseType::StateDependent >	
qpp::QubitAmplitudeDampingNoise	
qpp::QubitPhaseDampingNoise	
qpp::NoiseBase < NoiseType::StateIndependent >	
qpp::QubitBitFlipNoise	
qpp::QubitBitPhaseFlipNoise	
qpp::QubitDepolarizingNoise	
qpp::QubitPhaseFlipNoise	
qpp::QuditDepolarizingNoise	
qpp::NoiseType	46
$qpp::internal::Singleton < T > \dots \dots$	
$\label{lem:qpp::internal::Singleton} $$\operatorname{qpp::internal::Singleton} < \operatorname{const} Codes > \dots $	18
qpp::Codes	34
qpp::internal::Singleton < const Gates >	18
qpp::Gates	72
qpp::internal::Singleton< const Init >	
qpp::Init	
qpp::internal::Singleton < const States >	
qpp::States	
qpp::internal::Singleton < RandomDevices >	
qpp::RandomDevices	15
qpp::NoiseType::StateDependent	23
qpp::NoiseType::StateIndependent	
true_type	
$qpp::is_complex < std::complex < T >> \dots $	38
$qpp::is_iterable < \ T, \ to_void < \ decltype(std::declval < \ T \ > ().begin()), \ decltype(std::declval < \ T \)$	
>().end()), decltype(*(std::declval< T >().begin()))>>	10

Chapter 4

Class Index

4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

qpp::Bit_circuit	
Classical reversible circuit simulator	129
qpp::Codes	
Const Singleton class that defines quantum error correcting codes	134
qpp::exception::CustomException	
Custom exception	137
qpp::exception::DimsInvalid	
Invalid dimension(s) exception	140
qpp::exception::DimsMismatchCvector	
Dimension(s) mismatch column vector size exception	142
qpp::exception::DimsMismatchMatrix	
Dimension(s) mismatch matrix size exception	144
qpp::exception::DimsMismatchRvector	
Dimension(s) mismatch row vector size exception	146
qpp::exception::DimsMismatchVector	
Dimension(s) mismatch vector size exception	148
qpp::exception::DimsNotEqual	
Dimensions not equal exception	150
qpp::internal::Display_Impl	152
qpp::exception::Duplicates	
System (e.g. std::vector) has duplicates exception	153
qpp::Dynamic_bitset	
Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std←	
::bitset <n>)</n>	155
qpp::exception::Exception	
Base class for generating Quantum++ custom exceptions	166
qpp::Bit_circuit::Gate_count	170
qpp::Gates	
Const Singleton class that implements most commonly used gates	172
qpp::QCircuit::GateStep	
One step consisting only of gates/operators in the circuit	185
qpp::IDisplay	
Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream&	& os) cons
188	
qpp::IJSON	
Abstract class (interface) that mandates the definition of very basic JSON serialization support	191

8 Class Index

qpp::Init	
Const Singleton class that performs additional initializations/cleanups	193
qpp::exception::InvalidIterator	
Invalid iterator	
qpp::internal::IOManipEigen	197
qpp::internal::IOManipPointer< PointerType >	200
qpp::internal::IOManipRange< InputIterator >	203
qpp::is_complex < T >	
Checks whether the type is a complex type	207
qpp::is_complex < std::complex < T > >	
Checks whether the type is a complex number type, specialization for complex types	208
qpp::is_iterable< T, typename >	
Checks whether T is compatible with an STL-like iterable container	209
qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval< T >().end()), d	ecltype(*(std::declval<
Checks whether T is compatible with an STL-like iterable container, specialization for STL-like	
iterable containers	210
qpp::is_matrix_expression< Derived >	
Checks whether the type is an Eigen matrix expression	211
qpp::QCircuit::iterator	
Quantum circuit bound-checking (safe) iterator	212
qpp::make_void< Ts >	
Helper for qpp::to_void<> alias template	217
qpp::exception::MatrixMismatchSubsys	211
Matrix mismatch subsystems exception	218
qpp::exception::MatrixNotCvector	210
Matrix is not a column vector exception	220
qpp::exception::MatrixNotRvector	220
	222
Matrix is not a row vector exception	222
qpp::exception::MatrixNotSquare	004
Matrix is not square exception	224
qpp::exception::MatrixNotSquareNorCvector	000
Matrix is not square nor column vector exception	226
qpp::exception::MatrixNotSquareNorRvector	
Matrix is not square nor row vector exception	228
qpp::exception::MatrixNotSquareNorVector	
Matrix is not square nor vector exception	230
qpp::exception::MatrixNotVector	
Matrix is not a vector exception	232
qpp::QCircuit::MeasureStep	
One step consisting only of measurements in the circuit	234
qpp::exception::NoCodeword	
Codeword does not exist exception	237
qpp::NoiseBase< T >	
Base class for all noise models, derive your particular noise model	239
qpp::NoiseType	
Contains template tags used to specify the noise type	246
qpp::exception::NotBipartite	
Not bi-partite exception	247
qpp::exception::NotImplemented	
Code not yet implemented	249
qpp::exception::NotQubitCvector	
Column vector is not 2 x 1 exception	251
qpp::exception::NotQubitMatrix	
Matrix is not 2 x 2 exception	253
qpp::exception::NotQubitRvector	
Row vector is not 1 x 2 exception	255
qpp::exception::NotQubitSubsys	200
Subsystems are not qubits exception	257
Casofotomo aro not quento exception	

4.1 Class List

qpp::exception::NotQubitVector	
Vector is not 2 x 1 nor 1 x 2 exception	259
qpp::exception::OutOfRange	
Argument out of range exception	261
qpp::exception::PermInvalid	
Invalid permutation exception	263
qpp::exception::PermMismatchDims	
Permutation mismatch dimensions exception	265
qpp::QCircuit	
Quantum circuit class	267
qpp::QEngine	
Quantum circuit engine, executes qpp::QCircuit	292
qpp::QubitAmplitudeDampingNoise	
Qubit amplitude damping noise, as described in Nielsen and Chuang	301
qpp::QubitBitFlipNoise	
Qubit bit flip noise	302
qpp::QubitBitPhaseFlipNoise	
Qubit bit-phase flip (dephasing) noise	304
qpp::QubitDepolarizingNoise	
Qubit depolarizing noise	305
qpp::QubitPhaseDampingNoise	
Qubit phase damping noise, as described in Nielsen and Chuang	307
qpp::QubitPhaseFlipNoise	
Qubit phase flip (dephasing) noise	308
qpp::exception::QuditAlreadyMeasured	
Qudit was already measured exception	310
qpp::QuditDepolarizingNoise	
Qudit depolarizing noise	312
qpp::RandomDevices	
Singleton class that manages the source of randomness in the library	315
qpp::internal::Singleton< T >	
Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously	
recurring template pattern)	318
qpp::exception::SizeMismatch	
Size mismatch exception	321
qpp::NoiseType::StateDependent	
Template tag, used whenever the noise is state-dependent	323
qpp::NoiseType::StateIndependent	
Template tag, used whenever the noise is state-independent	323
qpp::States	
Const Singleton class that implements most commonly used states	323
qpp::exception::SubsysMismatchDims	
Subsystems mismatch dimensions exception	333
qpp::Timer< T, CLOCK T >	
Chronometer	335
qpp::exception::TypeMismatch	
Type mismatch exception	340
qpp::exception::UndefinedType	
Not defined for this type exception	342
qpp::exception::Unknown	
Unknown exception	344
qpp::QCircuit::iterator::value_type	346
qpp::exception::ZeroSize	.
Object has zero size exception	350

10 Class Index

Chapter 5

File Index

5.1 File List

Here is a list of all files with brief descriptions:

constar	nts.h	
	Constants	363
entangl	lement.h	
	Entanglement functions	364
entropie	es.h	
	Entropy functions	366
function		
	Generic quantum computing functions	367
input_o	output.h	
	Input/output functions	372
instrum	nents.h	
	Measurement functions	373
numbei	r_theory.h	
	Number theory functions	378
operation	ons.h	
	Quantum operation functions	380
qpp.h		
	Quantum++ main header file, includes all other necessary headers	382
random		
	Randomness-related functions	384
statistic		
	Statistics functions	386
traits.h		
	Type traits	387
types.h		
	Type aliases	388
classes	s/circuits.h	
	Support for qudit quantum circuits	353
classes	s/codes.h	
	Quantum error correcting codes	354
classes	s/exception.h	
	Exceptions	355
classes	s/gates.h	
	Quantum gates	357

12 File Index

classes/idisplay.h	
Display interface via the non-virtual interface (NVI) and very basic JSON serialization support	
interface	358
classes/init.h	
Initialization	358
classes/noise.h	
Noise models	359
classes/random_devices.h	
Random devices	360
classes/reversible.h	
Support for classical reversible circuits	361
classes/states.h	
Quantum states	361
classes/timer.h	
Timing	362
experimental/experimental.h	
Experimental/test functions/classes	367
internal/util.h	
Internal utility functions	376
internal/classes/iomanip.h	
Input/output manipulators	374
internal/classes/singleton.h	
Singleton pattern via CRTP	375
MATLAB/matlab.h	
Input/output interfacing with MATLAB	378

Chapter 6

Namespace Documentation

6.1 qpp Namespace Reference

Quantum++ main namespace.

Namespaces

· exception

Quantum++ exception hierarchy namespace.

· experimental

Experimental/test functions/classes, do not use or modify.

internal

Internal utility functions, do not use them directly or modify them.

literals

Classes

· class Bit_circuit

Classical reversible circuit simulator.

• class Codes

const Singleton class that defines quantum error correcting codes

· class Dynamic_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

· class Gates

const Singleton class that implements most commonly used gates

class IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

class IJSON

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

class Init

const Singleton class that performs additional initializations/cleanups

· struct is complex

Checks whether the type is a complex type.

- struct is_complex< std::complex< T > >

Checks whether the type is a complex number type, specialization for complex types.

· struct is_iterable

Checks whether T is compatible with an STL-like iterable container.

 $\bullet \ \ struct\ is_iterable < T,\ to_void < \ decltype(std::declval < T>().begin()),\ decltype(std::declval < T>().end()),\ decltype(*(std::declval < T>().end())),\ decltype(*(std::declval < T>().end()$

Checks whether T is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

• struct is_matrix_expression

Checks whether the type is an Eigen matrix expression.

· struct make void

Helper for qpp::to_void<> alias template.

· class NoiseBase

Base class for all noise models, derive your particular noise model.

class NoiseType

Contains template tags used to specify the noise type.

class QCircuit

Quantum circuit class.

· class QEngine

Quantum circuit engine, executes qpp::QCircuit.

· class QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

• class QubitBitFlipNoise

Qubit bit flip noise.

• class QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

· class QubitDepolarizingNoise

Qubit depolarizing noise.

· class QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

class QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

· class QuditDepolarizingNoise

Qudit depolarizing noise.

· class RandomDevices

Singleton class that manages the source of randomness in the library.

· class States

const Singleton class that implements most commonly used states

· class Timer

Chronometer.

Typedefs

```
• template<typename... Ts>
```

```
using to_void = typename make_void < Ts... >::type
```

Alias template that implements the proposal for void_t.

• using idx = std::size t

Non-negative integer index, make sure you use an unsigned type.

• using bigint = long long int

Big integer.

• using cplx = std::complex< double >

Complex number in double precision.

• using ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector. using bra = Eigen::RowVectorXcd Complex (double precision) dynamic Eigen row vector. • using cmat = Eigen::MatrixXcd Complex (double precision) dynamic Eigen matrix. using dmat = Eigen::MatrixXd Real (double precision) dynamic Eigen matrix. template<typename Scalar > using dyn mat = Eigen::Matrix < Scalar, Eigen::Dynamic, Eigen::Dynamic > Dynamic Eigen matrix over the field specified by Scalar. • template<typename Scalar > using dyn_col_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 > Dynamic Eigen column vector over the field specified by Scalar. template<typename Scalar > using dyn_row_vect = Eigen::Matrix < Scalar, 1, Eigen::Dynamic > Dynamic Eigen row vector over the field specified by Scalar. **Functions** • constexpr cplx operator"" _i (long double x) noexcept User-defined literal for complex $i = \sqrt{-1}$ (real overload) cplx omega (idx D) D-th root of unity. • template<typename Derived > dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt coefficients of the bi-partite pure state A. template<typename Derived > dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2) Schmidt coefficients of the bi-partite pure state A. template<typename Derived > cmat schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt basis on Alice side. • template<typename Derived > cmat schmidtA (const Eigen::MatrixBase< Derived > &A, idx d=2) Schmidt basis on Alice side. template<typename Derived > cmat schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt basis on Bob side. template<typename Derived > cmat schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2) Schmidt basis on Bob side. template<typename Derived > std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt probabilities of the bi-partite pure state A.

std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)

double entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)

template<typename Derived >

template<typename Derived >

Schmidt probabilities of the bi-partite pure state A.

Entanglement of the bi-partite pure state A.

```
• template<typename Derived >
  double entanglement (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Entanglement of the bi-partite pure state A.
template<typename Derived >
  double gconcurrence (const Eigen::MatrixBase< Derived > &A)
     G-concurrence of the bi-partite pure state A.
template<typename Derived >
  double negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Negativity of the bi-partite mixed state A.

    template < typename Derived >

  double negativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Negativity of the bi-partite mixed state A.

    template < typename Derived >

  double lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Logarithmic negativity of the bi-partite mixed state A.
• template<typename Derived >
  double lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Logarithmic negativity of the bi-partite mixed state A.
• template<typename Derived >
  double concurrence (const Eigen::MatrixBase< Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.
• template<typename Derived >
  double entropy (const Eigen::MatrixBase< Derived > &A)
      von-Neumann entropy of the density matrix A

    double entropy (const std::vector< double > &prob)

     Shannon entropy of the probability distribution prob.

    template<typename Derived >

  double renyi (const Eigen::MatrixBase< Derived > &A, double alpha)
      Renyi- \alpha entropy of the density matrix A, for \alpha \geq 0.

    double renyi (const std::vector< double > &prob, double alpha)

     Renyi- \alpha entropy of the probability distribution prob, for \alpha > 0.

    template<typename Derived >

  double tsallis (const Eigen::MatrixBase< Derived > &A, double q)
      Tsallis- q entropy of the density matrix A, for q > 0.

    double tsallis (const std::vector< double > &prob, double q)

      Tsallis- q entropy of the probability distribution prob, for q > 0.
• template<typename Derived >
  double qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx > &subsysB, const std::vector< idx > &dims)
     Quantum mutual information between 2 subsystems of a composite system.

    template<typename Derived >

  double gmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx> &subsysB, idx d=2)
      Quantum mutual information between 2 subsystems of a composite system.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > transpose (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > adjoint (const Eigen::MatrixBase< Derived > &A)
     Adjoint.
```

```
    template<typename Derived >

  dyn_mat< typename Derived::Scalar > inverse (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  Derived::Scalar trace (const Eigen::MatrixBase< Derived > &A)
      Trace
• template<typename Derived >
  Derived::Scalar det (const Eigen::MatrixBase< Derived > &A)
     Determinant.

    template<typename Derived >

  Derived::Scalar logdet (const Eigen::MatrixBase< Derived > &A)
     Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar sum (const Eigen::MatrixBase< Derived > &A)
      Element-wise sum of A.
• template<typename Derived >
  Derived::Scalar prod (const Eigen::MatrixBase< Derived > &A)
     Element-wise product of A.

    template<typename Derived >

  double norm (const Eigen::MatrixBase< Derived > &A)
     Frobenius norm.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > normalize (const Eigen::MatrixBase< Derived > &A)
     Normalizes state vector (column or row vector) or density matrix.

    template<typename Derived >

  std::pair < dyn_col_vect < cplx >, cmat > eig (const Eigen::MatrixBase < Derived > &A)
     Full eigen decomposition.

    template<typename Derived >

  dyn_col_vect< cplx > evals (const Eigen::MatrixBase< Derived > &A)
     Eigenvalues.

    template<typename Derived >

  cmat evects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors.

    template<typename Derived >

  std::pair< dyn_col_vect< double >, cmat > heig (const Eigen::MatrixBase< Derived > &A)
     Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > hevals (const Eigen::MatrixBase< Derived > &A)
     Hermitian eigenvalues.
• template<typename Derived >
  cmat hevects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors of Hermitian matrix.
• template<typename Derived >
  std::tuple< cmat, dyn_col_vect< double >, cmat > svd (const Eigen::MatrixBase< Derived > &A)
     Full singular value decomposition.

    template<typename Derived >

  dyn_col_vect< double > svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.
• template<typename Derived >
  cmat svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.

    template<typename Derived >

  cmat svdV (const Eigen::MatrixBase< Derived > &A)
```

Direct sum.

```
Right singular vectors.
• template<typename Derived >
  cmat funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)

    template<typename Derived >

  cmat sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.

    template<typename Derived >

  cmat absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.

    template<typename Derived >

  cmat expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.

    template<typename Derived >

  cmat logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.
• template<typename Derived >
  cmat sinm (const Eigen::MatrixBase< Derived > &A)
     Matrix sin.

    template<typename Derived >

  cmat cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.
template<typename Derived >
  cmat spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.
• template<typename Derived >
  \label{eq:const_equation} \mbox{dyn\_mat} < \mbox{typename Derived::Scalar} > \mbox{powm (const Eigen::MatrixBase} < \mbox{Derived} > \&\mbox{A, idx n)}
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.
• template<typename Derived >
  double schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const type-
  name Derived::Scalar &))
     Functor.
template<typename T >
  dyn_mat< typename T::Scalar > kron (const T &head)
     Kronecker product.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > kron (const T &head, const Args &... tail)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > kron (const std::vector< Derived > &As)
     Kronecker product.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > kron (const std::initializer_list< Derived > &As)
     Kronecker product.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Kronecker power.

    template<typename T >

  dyn_mat< typename T::Scalar > dirsum (const T &head)
```

```
• template<typename T, typename... Args>
  dyn_mat< typename T::Scalar > dirsum (const T &head, const Args &... tail)
     Direct sum.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > dirsum (const std::vector< Derived > &As)

    template<typename Derived >

  dyn mat< typename Derived::Scalar > dirsum (const std::initializer list< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > reshape (const Eigen::MatrixBase< Derived > &A, idx rows, idx
  cols)
     Reshape.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > comm (const Eigen::MatrixBase< Derived1 > &A, const Eigen::⊷
  MatrixBase< Derived2 > &B)
     Commutator.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > prj (const Eigen::MatrixBase< Derived > &A)
     Projector.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > grams (const std::vector< Derived > &As)
     Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > grams (const std::initializer_list< Derived > &As)
      Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > grams (const Eigen::MatrixBase< Derived > &A)
     Gram-Schmidt orthogonalization.

    std::vector< idx > n2multiidx (idx n, const std::vector< idx > &dims)

     Non-negative integer index to multi-index.

    idx multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

     Multi-index to non-negative integer index.

    ket mket (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Multi-partite qudit ket.

    ket mket (const std::vector< idx > &mask, idx d=2)

     Multi-partite qudit ket.

    cmat mprj (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Projector onto multi-partite qudit ket.

    cmat mprj (const std::vector < idx > &mask, idx d=2)

     Projector onto multi-partite qudit ket.
• template<typename InputIterator >
  std::vector< double > abssq (InputIterator first, InputIterator last)
```

Computes the absolute values squared of an STL-like range of complex numbers.

• template<typename Container >

std::vector< double > abssq (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Computes the absolute values squared of an STL-like container.

template<typename Derived >

```
std::vector< double > abssq (const Eigen::MatrixBase< Derived > &A)
```

Computes the absolute values squared of an Eigen expression.

template<typename InputIterator >

std::iterator_traits< InputIterator >::value_type sum (InputIterator first, InputIterator last)

Element-wise sum of an STL-like range.

• template<typename Container >

Container::value_type sum (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

std::iterator traits < InputIterator >::value type prod (InputIterator first, InputIterator last)

Element-wise product of an STL-like range.

• template<typename Container >

Container::value_type prod (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Element-wise product of the elements of an STL-like container.

template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > rho2pure (const Eigen::MatrixBase< Derived > &A)
```

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

std::vector< idx > complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

• template<typename Derived >

```
std::vector< double > rho2bloch (const Eigen::MatrixBase< Derived > &A)
```

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

• template<typename Derived >

internal::IOManipEigen disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)

Eigen expression ostream manipulator.

internal::IOManipEigen disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

• template<typename InputIterator >

internal::IOManipRange < InputIterator > disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")

Range ostream manipulator.

 $\bullet \ \ \text{template}{<} \text{typename Container} >$

internal::IOManipRange< typename Container::const_iterator > disp (const Container &c, const std::string &separator, const std::string &start="[", const std::string &end="]", typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

template<typename PointerType >

internal::IOManipPointer< PointerType > disp (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")

C-style pointer ostream manipulator.

template<typename Derived >

```
void save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)
```

Saves Eigen expression to a binary file (internal format) in double precision.

template<typename Derived >

dyn_mat< typename Derived::Scalar > load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.

• template<typename Derived >

 $\label{lem:dyn_col_vect} $$ \displaystyle \operatorname{dyn_col_vect} < \operatorname{typename \ Derived}::Scalar > ip (const \ Eigen::MatrixBase < \operatorname{Derived} > & phi, const \ Eigen:: \longleftrightarrow \\ \operatorname{MatrixBase} < \operatorname{Derived} > & psi, const \ std::vector < idx > & subsys, const \ std::vector < idx > & dims) \\ $$ \displaystyle \operatorname{dyn_col_vect} < \operatorname{dyn_col_v$

Generalized inner product.

• template<typename Derived >

dyn_col_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template<typename Derived >

 $std::tuple < std::vector < idx >, \ double, \ cmat > measure_seq \ (const \ Eigen::MatrixBase < Derived > \&A, \\ std::vector < idx > target, \ idx \ d=2)$

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

ullet template<typename Derived >

 $std::enable_if < std::is_same < typename Derived::Scalar, cplx >::value, dyn_mat < cplx > ::type \\ loadMATLAB (const std::string &mat_file, const std::string &var_name)$

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::

Scalar > >::type loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

std::vector< int > x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

bigint gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > invperm (const std::vector< idx > &perm)

Inverse permutation.

• std::vector< idx > compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

std::vector< bigint > factors (bigint a)

Prime factor decomposition.

• bigint modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

bigint modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple < bigint, bigint, bigint > egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint modinv (bigint a, bigint p)

Modular inverse of a mod p.

bool isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

bigint randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

std::vector< std::pair< int, int > > convergents (const std::vector< int > &cf)

Convergents

std::vector< std::pair< int, int > > convergents (double x, idx N)

Convergents.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, const
std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

- template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, idx
d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)
```

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

template<typename Derived >

cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, const std::vector< idx > &dims)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

• template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, idx d=2)
```

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat kraus2super (const std::vector < cmat > &Ks)

Superoperator matrix.

cmat kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector< cmat > choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

template<typename Derived >

```
\label{lem:dyn_mat}  \mbox{dyn\_mat} < \mbox{typename Derived::Scalar} > \mbox{ptrace1} \mbox{ (const Eigen::MatrixBase} < \mbox{Derived} > \&\mbox{A, const std} \\ \mbox{::vector} < \mbox{idx} > \&\mbox{dims})
```

Partial trace.

 $\bullet \ \ {\sf template}{<} {\sf typename \ Derived} >$

```
dyn_mat< typename Derived::Scalar > ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.
```

template<typename Derived >

```
\frac{dyn\_mat<}{typename} \ Derived::Scalar > ptrace2 \ (const \ Eigen::MatrixBase< \ Derived > \&A, \ const \ std \\ \because vector < idx > \&dims)
```

Partial trace.

• template<typename Derived >

```
dyn_mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)
```

Partial trace.

ullet template<typename Derived >

 $\frac{dyn_mat}{dx}$ typename Derived::Scalar > $\frac{dyn_mat}{dx}$ (const Eigen::MatrixBase < Derived > &A, const std::vector < $\frac{dx}{dx}$ > &target, const std::vector < $\frac{dx}{dx}$ > &dims)

Partial trace.

ullet template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector
idx > &target, idx d=2)

Partial trace.

template<typename Derived >

Partial transpose.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptranspose (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial transpose.

• template<typename Derived >

Subsystem permutation.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > syspermute (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &perm, idx d=2)

Subsystem permutation.

template<typename Derived >

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_mat< typename Derived::Scalar > applyTFQ (const Eigen::MatrixBase< Derived > &A, const std↔ ::vector< idx > &target, idx d=2, bool swap=true)

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool
swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool
swap=true)

Qudit quantum Fourier transform.

• double rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

• bigint rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx randidx (idx a=std::numeric_limits < idx >::min(), idx b=std::numeric_limits < idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

Derived rand (idx rows, idx cols, double a=0, double b=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

• template<>

dmat rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (gpp::dmat)

• template<>

cmat rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived randn (idx rows, idx cols, double mean=0, double sigma=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

dmat randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

template<>

cmat randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

• double randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

• cmat randU (idx D=2)

Generates a random unitary matrix.

· cmat randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat randH (idx D=2)

Generates a random Hermitian matrix.

• ket randket (idx D=2)

Generates a random normalized ket (pure state vector)

cmat randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.

std::vector< double > uniform (idx N)

Uniform probability distribution vector.

std::vector< double > marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > marginalY (const dmat &probXY)

Marginal distribution.

 $\bullet \ \ \text{template}{<} \text{typename Container} >$

double avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable<
Container >::value >::type *=nullptr)

Average.

• template<typename Container >

double cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is iterable< Container >::value >::type *=nullptr)

Covariance.

• template<typename Container >

double var (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable<
Container >::value >::type *=nullptr)

Variance.

template<typename Container >
 double sigma (const std::vector< double > &prob, const Container &X, typename std::enable_if<
 is_iterable< Container >::value >::type *=nullptr)

Standard deviation.

• template<typename Container >

double cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Correlation.

Variables

• constexpr double chop = 1e-10

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

constexpr double eps = std::numeric_limits<double>::epsilon()

Used to decide whether a number or expression in double precision is zero or not for the purpose of a specific computation.

• constexpr idx maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

constexpr double pi = 3.141592653589793238462643383279502884

 π

constexpr double ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

constexpr double infty = std::numeric_limits<double>::max()

Used to denote infinity in double precision.

const idx idx infty = static cast<idx>(-1)

Used to denote the largest unsigned index.

6.1.1 Detailed Description

Quantum++ main namespace.

6.1.2 Typedef Documentation

6.1.2.1 bigint

```
using qpp::bigint = typedef long long int
```

Big integer.

6.1.2.2 bra

```
using qpp::bra = typedef Eigen::RowVectorXcd
```

Complex (double precision) dynamic Eigen row vector.

```
6.1.2.3 cmat
```

```
using qpp::cmat = typedef Eigen::MatrixXcd
```

Complex (double precision) dynamic Eigen matrix.

6.1.2.4 cplx

```
using qpp::cplx = typedef std::complex<double>
```

Complex number in double precision.

6.1.2.5 dmat

```
using qpp::dmat = typedef Eigen::MatrixXd
```

Real (double precision) dynamic Eigen matrix.

6.1.2.6 dyn_col_vect

```
template<typename Scalar >
using qpp::dyn_col_vect = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, 1>
```

Dynamic Eigen column vector over the field specified by Scalar.

Example:

```
// type of colvect is Eigen::Matrix<float, Eigen::Dynamic, 1>
dyn_col_vect<float> colvect(2);
```

6.1.2.7 dyn_mat

```
template<typename Scalar >
using qpp::dyn_mat = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, Eigen::Dynamic>
```

Dynamic Eigen matrix over the field specified by Scalar.

Example:

```
// type of mat is Eigen::Matrix<float, Eigen::Dynamic, Eigen::Dynamic>
dyn_mat<float> mat(2, 3);
```

```
6.1.2.8 dyn_row_vect
```

```
template<typename Scalar >
using qpp::dyn_row_vect = typedef Eigen::Matrix<Scalar, 1, Eigen::Dynamic>
```

Dynamic Eigen row vector over the field specified by Scalar.

Example:

```
// type of rowvect is Eigen::Matrix<float, 1, Eigen::Dynamic>
dyn_row_vect<float> rowvect(3);
```

6.1.2.9 idx

```
using qpp::idx = typedef std::size_t
```

Non-negative integer index, make sure you use an unsigned type.

6.1.2.10 ket

```
using qpp::ket = typedef Eigen::VectorXcd
```

Complex (double precision) dynamic Eigen column vector.

6.1.2.11 to_void

```
template<typename... Ts>
using qpp::to_void = typedef typename make_void<Ts...>::type
```

Alias template that implements the proposal for void_t.

See also

```
http://www.open-std.org/jtc1/sc22/wg21/docs/papers/2014/n3911
```

6.1.3 Function Documentation

6.1.3.1 absm()

Matrix absolute value.

Parameters

```
A Eigen expression
```

Returns

Matrix absolute value of A

Computes the absolute values squared of an STL-like range of complex numbers.

Parameters

	Iterator to the first element of the range
last	Iterator to the last element of the range

InputIterator last)

Returns

Real vector consisting of the range absolute values squared

```
6.1.3.3 abssq() [2/3]
```

Computes the absolute values squared of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Real vector consisting of the container's absolute values squared

Computes the absolute values squared of an Eigen expression.

Parameters

```
A Eigen expression
```

Returns

Real vector consisting of the absolute values squared

6.1.3.5 adjoint()

Adjoint.

Parameters

```
A Eigen expression
```

Returns

Adjoint (Hermitian conjugate) of A, as a dynamic matrix over the same scalar field as A

6.1.3.6 anticomm()

Anti-commutator.

See also

qpp::comm()

Anti-commutator $\{A,B\} = AB + BA$. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
В	Eigen expression

Returns

Anti-commutator AB + BA, as a dynamic matrix over the same scalar field as A

6.1.3.7 apply() [1/5]

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

Returns

Gate A applied to the part target of state

6.1.3.8 apply() [2/5]

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

Returns

Gate A applied to the part target of state

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes where the Kraus operators Ks are applied
dims	Dimensions of the multi-partite system

Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes where the Kraus operators Ks are applied
d	Subsystem dimensions

Returns

Output density matrix after the action of the channel

6.1.3.12 applyCTRL() [1/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate *A* must match the dimension of *target*. Also, all control subsystems in *ctrl* must have the same dimension.

Parameters

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

Returns

CTRL-A gate applied to the part target of state

6.1.3.13 applyCTRL() [2/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

Returns

CTRL-A gate applied to the part target of state

6.1.3.14 applyQFT()

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

Parameters

Α	Eigen expression
target	Subsystem indexes where the QFT is applied
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Qudit Quantum Fourier transform applied to the part target of A

6.1.3.15 applyTFQ()

Applies the inverse (adjoint) qudit quantum Fourier transform to the part *target* of the multi-partite state vector or density matrix *A*.

Parameters

Α	Eigen expression
target	Subsystem indexes where the TFQ is applied
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Inverse (adjoint) qudit Quantum Fourier transform applied to the part target of A

6.1.3.16 avg()

Average.

Parameters

prob	Real probability vector representing the probability distribution of X
Χ	Real random variable values represented by an STL-like container

Returns

Average of X

6.1.3.17 bloch2rho()

Computes the density matrix corresponding to the 3-dimensional real Bloch vector *r*.

See also

qpp::rho2bloch()

Parameters

r 3-dimensional real vector

Returns

Qubit density matrix

6.1.3.18 choi2kraus()

Orthogonal Kraus operators from Choi matrix.

See also

qpp::kraus2choi()

Extracts a set of orthogonal (under Hilbert-Schmidt operator norm) Kraus operators from the Choi matrix A

Note

The Kraus operators satisfy $Tr(K_i^{\dagger}K_j)=\delta_{ij}$ for all $i\neq j$

Parameters



Returns

Set of orthogonal Kraus operators


6.1.3.19 choi2super()

Converts Choi matrix to superoperator matrix.

See also

qpp::super2choi()

Parameters



Returns

Superoperator matrix

6.1.3.20 comm()

Commutator.

See also

qpp::anticomm()

Commutator [A, B] = AB - BA. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
В	Eigen expression

Returns

Commutator AB - BA, as a dynamic matrix over the same scalar field as A

6.1.3.21 complement()

Constructs the complement of a subsystem vector.

Parameters

subsys	Subsystem vector
n	Total number of systems

Returns

Complement of *subsys* with respect to the set $\{0, 1, \dots, n-1\}$

6.1.3.22 compperm()

Compose permutations.

Parameters

perm	Permutation
sigma	Permutation

Returns

Composition of the permutations *perm* o *sigma* = perm(sigma)

6.1.3.23 concurrence()

Wootters concurrence of the bi-partite qubit mixed state A.

Parameters

```
A Eigen expression
```

Returns

Wootters concurrence

6.1.3.24 conjugate()

Complex conjugate.

Parameters

```
A Eigen expression
```

Returns

Complex conjugate of A, as a dynamic matrix over the same scalar field as A

6.1.3.25 contfrac2x()

Real representation of a simple continued fraction.

See also

```
qpp::x2contfrac()
```

Note

If N is greater than the size of cf (by default it is), then all terms in cf are considered.

Parameters

	Integer vector containing the simple continued fraction expansion
Ν	Number of terms considered in the continued fraction expansion.

Returns

Real representation of the simple continued fraction

6.1.3.26 convergents() [1/2]

```
std::vector<std::pair<int, int> > qpp::convergents ( const std::vector< int > & cf ) [inline]
```

Convergents.

See also

```
qpp::contfrac2x() and qpp::x2contfrac()
```

Parameters

```
cf Continued fraction
```

Returns

Vector of convergents pairs (a_k, b_k) that approximate the number represented by the continued fraction

6.1.3.27 convergents() [2/2]

```
std::vector<std::pair<int, int> > qpp::convergents ( double x, idx N) [inline]
```

Convergents.

See also

```
qpp::contfrac2x() and qpp::x2contfrac()
```

Note

In the continued fraction expansion of x has less terms than N, then the series of convergents is truncated to the number of terms in the continued fraction expansion of x.

Parameters

Х	Real number
Ν	Number of convergents.

Returns

Vector of convergents pairs (a_k,b_k) that approximate the number \emph{x}

6.1.3.28 cor()

Correlation.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels the rows, Y labels the columns)
X	Real random variable values represented by an STL-like container
Y	Real random variable values represented by an STL-like container

Returns

Correlation of X and Y

6.1.3.29 cosm()

Matrix cos.

Parameters

```
A Eigen expression
```

Returns

Matrix cosine of A

6.1.3.30 cov()

Covariance.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels the rows, Y labels the columns)
Χ	Real random variable values represented by an STL-like container
Y	Real random variable values represented by an STL-like container

Returns

Covariance of X and Y

6.1.3.31 cwise()

Functor.

Parameters

Α	Eigen expression
f	Pointer-to-function from scalars of A to OutputScalar

Returns

Component-wise f(A), as a dynamic matrix over the *OutputScalar* scalar field

6.1.3.32 det()

Determinant.

Parameters

A Eigen expression

Returns

Determinant of A, as a scalar over the same scalar field as A. Returns $\pm \infty$ when the determinant overflows/underflows.

```
6.1.3.33 dirsum() [1/4]
```

Direct sum.

See also

qpp::dirsumpow()

Used to stop the recursion for the variadic template version of qpp::dirsum()

Parameters

head	Eigen expression
ncau	Ligon capicosion

Its argument head

Direct sum.

See also

qpp::dirsumpow()

Parameters

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

Returns

Direct sum of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

```
6.1.3.35 dirsum() [3/4]
```

Direct sum.

See also

qpp::dirsumpow()

Parameters

As std::vector of Eigen expressions

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Direct sum.

See also

qpp::dirsumpow()

Parameters

As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}

Returns

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.3.37 dirsumpow()

Direct sum power.

See also

qpp::dirsum()

Parameters

Α	Eigen expression
n	Non-negative integer

Direct sum of A with itself n times $A^{\oplus n}$, as a dynamic matrix over the same scalar field as A

Eigen expression ostream manipulator.

Parameters

Α	Eigen expression
chop	Set to zero the elements smaller in absolute value than <i>chop</i>

Returns

Instance of qpp::internal::IOManipEigen

Complex number ostream manipulator.

Parameters

Z	Complex number (or any other type implicitly cast-able to std::complex <double>)</double>
chop	Set to zero the elements smaller in absolute value than chop

Returns

Instance of qpp::internal::IOManipEigen

```
6.1.3.40 disp() [3/5]

template<typename InputIterator >
internal::IOManipRange<InputIterator> qpp::disp (
```

```
InputIterator first,
InputIterator last,
const std::string & separator,
const std::string & start = "[",
const std::string & end = "]")
```

Range ostream manipulator.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipRange

```
6.1.3.41 disp() [4/5]
```

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

Parameters

С	Container
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipRange

6.1.3.42 disp() [5/5]

```
template<typename PointerType >
internal::IOManipPointer<PointerType> qpp::disp (
```

```
const PointerType * p,
idx N,
const std::string & separator,
const std::string & start = "[",
const std::string & end = "]")
```

C-style pointer ostream manipulator.

Parameters

р	Pointer to the first element
N	Number of elements to be displayed
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipPointer

6.1.3.43 egcd()

Extended greatest common divisor of two integers.

See also

qpp::gcd()

Parameters

а	Integer
b	Integer

Returns

Tuple of: 1. Integer m, 2. Integer n, and 3. Non-negative integer gcd(a,b) such that ma + nb = gcd(a,b)

6.1.3.44 eig()

Full eigen decomposition.

See also

qpp::heig()

Parameters

```
A Eigen expression
```

Returns

Pair of: 1. Eigenvalues of *A*, as a complex dynamic column vector, and 2. Eigenvectors of *A*, as columns of a complex dynamic matrix

6.1.3.45 entanglement() [1/2]

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

```
qpp::entropy()
```

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Entanglement, with the logarithm in base 2

6.1.3.46 entanglement() [2/2]

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

qpp::entropy()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Entanglement, with the logarithm in base 2

6.1.3.47 entropy() [1/2]

von-Neumann entropy of the density matrix A

Parameters

```
A Eigen expression
```

Returns

von-Neumann entropy, with the logarithm in base 2

6.1.3.48 entropy() [2/2]

Shannon entropy of the probability distribution prob.

Parameters

prob Real probability vector

Returns

Shannon entropy, with the logarithm in base 2

```
6.1.3.49 evals()
```

Eigenvalues.

See also

qpp::hevals()

Parameters

```
A Eigen expression
```

Returns

Eigenvalues of A, as a complex dynamic column vector

6.1.3.50 evects()

Eigenvectors.

See also

qpp::hevects()

Parameters

```
A Eigen expression
```

Returns

Eigenvectors of A, as columns of a complex dynamic matrix

6.1.3.51 expm()

Matrix exponential.

Parameters

A Eigen expression

Returns

Matrix exponential of A

6.1.3.52 factors()

Prime factor decomposition.

Note

Runs in $\mathcal{O}(\sqrt{n})$ time complexity

Parameters

a Integer different from 0, 1 or -1

Returns

Integer vector containing the factors

6.1.3.53 funm()

Functional calculus f(A)

Parameters

Α	Eigen expression
f	Pointer-to-function from complex to complex

```
Returns
```

```
f(A)
```

Greatest common divisor of two integers.

See also

```
qpp::lcm()
```

Parameters

а	Integer
b	Integer

Returns

Greatest common divisor of a and b

Greatest common divisor of a list of integers.

See also

```
qpp::lcm()
```

Parameters

```
as List of integers
```

Returns

Greatest common divisor of all numbers in as

6.1.3.56 gconcurrence()

G-concurrence of the bi-partite pure state A.

Note


Both local dimensions must be equal

Uses qpp::logdet() to avoid overflows

See also

qpp::logdet()

Parameters



Returns

G-concurrence

```
6.1.3.57 grams() [1/3]
```

Gram-Schmidt orthogonalization.

Parameters

```
As std::vector of Eigen expressions as column vectors
```

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

```
6.1.3.58 grams() [2/3]
```

Gram-Schmidt orthogonalization.

Parameters

```
As std::initializer_list of Eigen expressions as column vectors
```

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

Gram-Schmidt orthogonalization.

Parameters

A Eigen expression, the input vectors are the columns of A

Returns

Gram-Schmidt vectors of the columns of A, as columns of a dynamic matrix over the same scalar field as A

6.1.3.60 heig()

Full eigen decomposition of Hermitian expression.

See also

qpp::eig()

Parameters

A Eigen expression

Pair of: 1. Eigenvalues of A, as a real dynamic column vector, and 2. Eigenvectors of A, as columns of a complex dynamic matrix

6.1.3.61 hevals()

Hermitian eigenvalues.

See also

qpp::evals()

Parameters

A Eigen expression

Returns

Eigenvalues of Hermitian A, as a real dynamic column vector

6.1.3.62 hevects()

Eigenvectors of Hermitian matrix.

See also

qpp::evects()

Parameters

A Eigen expression

Returns

Eigenvectors of Hermitian matrix A, as columns of a complex matrix

6.1.3.63 inverse()

Inverse.

Parameters

```
A Eigen expression
```

Returns

Inverse of A, as a dynamic matrix over the same scalar field as A

6.1.3.64 invperm()

```
\label{eq:std:vector} $$ std::vector < idx > & perm ) $$ [inline] $$
```

Inverse permutation.

Parameters

perm Permut	ation
-------------	-------

Returns

Inverse of the permutation perm

6.1.3.65 ip() [1/2]

Generalized inner product.

Parameters

phi	hi Column vector Eigen expression	
psi	Column vector Eigen expression	
subsys	Subsystem indexes over which phi is defined	
dims	Dimensions of the multi-partite system	

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

Generalized inner product.

Parameters

phi	Column vector Eigen expression
psi	Column vector Eigen expression
subsys	Subsystem indexes over which phi is defined
d	Subsystem dimensions

Returns

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

6.1.3.67 isprime()

Primality test based on the Miller-Rabin's algorithm.

Parameters

p	Integer different from 0, 1 or -1
k	Number of iterations. The probability of a false positive is 2^{-k} .

Returns

True if the number is (most-likely) prime, false otherwise

6.1.3.68 kraus2choi()

Choi matrix.

See also

qpp::choi2kraus()

Constructs the Choi matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|, |0\rangle\langle 1|$ etc.

Note

The superoperator matrix S and the Choi matrix C are related by $S_{ab,mn}=C_{ma,nb}$

Parameters

Ks Set of Kraus operators

Returns

Choi matrix

6.1.3.69 kraus2super()

Superoperator matrix.

Constructs the superoperator matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|$, $|0\rangle\langle 1|$ etc.

Parameters

Ks Set of Kraus operators

Returns

Superoperator matrix

Kronecker product.

See also

qpp::kronpow()

Used to stop the recursion for the variadic template version of app::kron()

Parameters

head	Eigen expression
------	------------------

Returns

Its argument head

```
6.1.3.71 kron() [2/4]
```

Kronecker product.

See also

qpp::kronpow()

Parameters

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

Returns

Kronecker product of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

See also

qpp::kronpow()

Parameters

As std::vector of Eigen expressions

Returns

Kronecker product of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Kronecker product.

See also

qpp::kronpow()

Parameters

As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}

Returns

Kronecker product of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.3.74 kronpow()

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::kronpow (
```

```
const Eigen::MatrixBase< Derived > & A, idx n)
```

Kronecker power.

See also

qpp::kron()

Parameters

Α	Eigen expression
n	Non-negative integer

Returns

Kronecker product of A with itself n times $A^{\otimes n}$, as a dynamic matrix over the same scalar field as A

Least common multiple of two integers.

See also

qpp::gcd()

Parameters

а	Integer
b	Integer

Returns

Least common multiple of a and b

Least common multiple of a list of integers.

See also

```
qpp::gcd()
```

Parameters

```
as List of integers
```

Returns

Least common multiple of all numbers in as

6.1.3.77 load()

Loads Eigen matrix from a binary file (internal format) in double precision.

See also

```
qpp::save()
```

The template parameter cannot be automatically deduced and must be explicitly provided, depending on the scalar field of the matrix that is being loaded.

Example:

```
// loads a previously saved Eigen dynamic complex matrix from "input.bin" cmat mat = load<cmat>("input.bin");
```

Parameters

```
fname Output file name
```

6.1.3.78 loadMATLAB() [1/2]

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

```
qpp::saveMATLAB()
```

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen ket
// from the MATLAB file "input.mat"
ket psi = loadMATLABket>("input.mat");
```

Template Parameters

Derived	Complex Eigen type
---------	--------------------

Parameters

mat_file	MATALB .mat file	
var_name	Variable name in the .mat file representing the matrix to be loaded]

Returns

Eigen dynamic matrix

6.1.3.79 loadMATLAB() [2/2]

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

```
qpp::saveMATLAB()
```

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen dynamic double matrix
// from the MATLAB file "input.mat"
dmat mat = loadMATLAB<dmat>("input.mat");
```

Template Parameters

е
е

Parameters

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be loaded

Returns

Eigen dynamic matrix

6.1.3.80 logdet()

Logarithm of the determinant.

Useful when the determinant overflows/underflows

Parameters

```
A Eigen expression
```

Returns

Logarithm of the determinant of A, as a scalar over the same scalar field as A

6.1.3.81 logm()

Matrix logarithm.

Parameters

A Eigen expression

Matrix logarithm of A

Logarithmic negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Logarithmic negativity, with the logarithm in base 2

6.1.3.83 lognegativity() [2/2]

```
template<typename Derived >
double qpp::lognegativity (
          const Eigen::MatrixBase< Derived > & A,
          idx d = 2 )
```

Logarithmic negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Logarithmic negativity, with the logarithm in base 2

6.1.3.84 marginalX()

Marginal distribution.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels	1
	the rows, Y labels the columns)	

Returns

Real vector consisting of the marginal distribution of X

6.1.3.85 marginalY()

Marginal distribution.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels	
	the rows, Y labels the columns)	

Returns

Real vector consisting of the marginal distribution of Y

6.1.3.86 measure() [1/9]

Measures the state vector or density operator A using the set of Kraus operators Ks.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.87 measure() [2/9]

Measures the state vector or density matrix A using the set of Kraus operators Ks.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.88 measure() [3/9]

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

Parameters

Α	Eigen expression	
U	Unitary matrix whose columns represent the measurement basis vectors	

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.89 measure() [4/9]

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.90 measure() [5/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.92 measure() [7/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.93 measure() [8/9]

Measures the part *target* of the multi-partite state vector or density matrix *A* in the orthonormal basis or rank-1 projectors specified by the columns of the matrix *V*.

See also

```
qpp::measure_seq()
```

Note

The dimension of V must match the dimension of target. The measurement is destructive, i.e. the measured subsystems are traced away.

Α	Eigen expression
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part *target* of the multi-partite state vector or density matrix *A* in the orthonormal basis or rank-1 projectors specified by the columns of the matrix *V*.

See also

```
qpp::measure_seq()
```

Note

The dimension of *V* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression	
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors	
target	Subsystem indexes that are measured	
d	Subsystem dimensions	

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

See also

qpp::measure()

Parameters

Α	Eigen expression
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

See also

qpp::measure()

Parameters

Α	Eigen expression
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|\text{mask}\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

Parameters

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

Returns

Multi-partite qudit state vector, as a complex dynamic column vector

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Multi-partite qudit state vector, as a complex dynamic column vector

6.1.3.99 modinv()

Modular inverse of a mod p.

See also

```
qpp::egcd()
```

Note

a and p must be co-prime

Parameters

а	Non-negative integer
р	Non-negative integer

Returns

```
Modular inverse a^{-1} \mod p
```

6.1.3.100 modmul()

```
bigint qpp::modmul (
                bigint a,
                bigint b,
                bigint p ) [inline]
```

Modular multiplication without overflow.

Computes $ab \bmod p$ without overflow

Parameters

а	Integer
b	Integer
р	Positive integer

Returns

 $ab \bmod p$ avoiding overflow

6.1.3.101 modpow()

```
bigint qpp::modpow (
          bigint a,
```

```
bigint n,
bigint p ) [inline]
```

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

Note

Uses qpp::modmul() that avoids overflows

Computes $a^n \bmod p$

Parameters

а	Non-negative integer
n	Non-negative integer
р	Strictly positive integer

Returns

```
a^n \bmod p
```

const std::vector< idx > & dims) [inline]

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

Parameters

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

6.1.3.104 multiidx2n()

Multi-index to non-negative integer index.

See also

```
qpp::n2multiidx()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

Parameters

midx	Multi-index
dims	Dimensions of the multi-partite system

Returns

Non-negative integer index

6.1.3.105 n2multiidx()

```
\label{eq:std::vector} $$ std::vector < idx > qpp::n2multiidx ($$ idx n,$$ const std::vector < idx > & dims ) [inline]
```

Non-negative integer index to multi-index.

See also

```
qpp::multiidx2n()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

Parameters

n	Non-negative integer index
dims	Dimensions of the multi-partite system

Returns

Multi-index of the same size as dims

6.1.3.106 negativity() [1/2]

Negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Negativity

6.1.3.107 negativity() [2/2]

```
template<typename Derived >
double qpp::negativity (
```

```
const Eigen::MatrixBase< Derived > & A, idx d = 2)
```

Negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Negativity

6.1.3.108 norm()

Frobenius norm.

Parameters

```
A Eigen expression
```

Returns

Frobenius norm of A

6.1.3.109 normalize()

Normalizes state vector (column or row vector) or density matrix.

Parameters

A Eigen expression

Normalized state vector or density matrix

```
6.1.3.110 omega()

cplx qpp::omega (
          idx D ) [inline]
```

D-th root of unity.

Parameters

D Non-negative integer

6.1.3.111 operator""" _i()

Returns

D-th root of unity $\exp(2\pi i/D)$

User-defined literal for complex $i = \sqrt{-1}$ (real overload)

Example:

```
cplx z = 4.5_i; // type of z is std::complex<double>
```

6.1.3.112 powm()

Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

See also

```
qpp::spectralpowm()
```

Explicitly multiplies the matrix A with itself n times. By convention $A^0 = I$.

Α	Eigen expression
n	Non-negative integer

Returns

Matrix power A^n , as a dynamic matrix over the same scalar field as A

6.1.3.113 prj()

Projector.

Normalized projector onto state vector

Parameters

```
A Eigen expression
```

Returns

Projector onto the state vector A, or the matrix Zero if A has norm zero (i.e. smaller than qpp::eps), as a dynamic matrix over the same scalar field as A

6.1.3.114 prod() [1/3]

Element-wise product of A.

Parameters

```
A Eigen expression
```

Returns

Element-wise product of A, as a scalar over the same scalar field as A

Element-wise product of an STL-like range.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

InputIterator last)

Returns

Element-wise product of the range, as a scalar over the same scalar field as the range

Element-wise product of the elements of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Element-wise product of the elements of the container, as a scalar over the same scalar field as the container

See also

Partial trace.

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Returns

Partial trace $Tr_{subsys}(\cdot)$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

Partial trace.

See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial trace $Tr_{subsys}(\cdot)$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

```
6.1.3.119 ptrace1() [1/2]
```

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_A(\cdot)$ over the first subsytem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.120 ptrace1() [2/2]

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_A(\cdot)$ over the first subsystem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.121 ptrace2() [1/2]

Partial trace.

See also

```
qpp::ptrace1()
```

Partial trace over the second subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_B(\cdot)$ over the second subsytem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.122 ptrace2() [2/2]

Partial trace.

See also

qpp::ptrace1()

Partial trace over the second subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_B(\cdot)$ over the second subsytem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.123 ptranspose() [1/2]

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::ptranspose (
```

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & target,
const std::vector< idx > & dims )
```

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.3.124 ptranspose() [2/2]

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.3.125 QFT()

```
template<typename Derived >
dyn_col_vect<typename Derived::Scalar> qpp::QFT (
```

```
const Eigen::MatrixBase< Derived > & A, idx d = 2, bool swap = true)
```

Qudit quantum Fourier transform.

Parameters

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Qudit quantum Fourier transform applied on A

6.1.3.126 qmutualinfo() [1/2]

Quantum mutual information between 2 subsystems of a composite system.

Parameters

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
dims	Dimensions of the multi-partite system

Returns

Mutual information between the 2 subsystems

6.1.3.127 qmutualinfo() [2/2]

Quantum mutual information between 2 subsystems of a composite system.

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
d	Subsystem dimensions

Returns

Mutual information between the 2 subsystems

Generates a random real number uniformly distributed in the interval [a, b)

Parameters

a	ì	Beginning of the interval, belongs to it
b)	End of the interval, does not belong to it

Returns

Random real number (double) uniformly distributed in the interval [a, b)

Generates a random big integer uniformly distributed in the interval [a, b].

Note

To avoid ambiguity with double qpp::rand(double, double) cast at least one of the arguments to qpp::bigint

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

Random big integer uniformly distributed in the interval [a, b]

Generates a random matrix with entries uniformly distributed in the interval [a, b)

If complex, then both real and imaginary parts are uniformly distributed in [a, b)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries uniformly distributed in [-1,1)
dmat mat = rand<dmat>(3, 3, -1, 1);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd,
// with entries (both real and imaginary) uniformly distributed in [-1,1)
cmat mat = rand<cmat>(3, 3, -1, 1);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Returns

Random complex matrix

6.1.3.133 randH()

```
cmat qpp::randH (
    idx D = 2) [inline]
```

Generates a random Hermitian matrix.

Parameters

D Dimension of the Hilbert space

Random Hermitian matrix

6.1.3.134 randidx()

```
idx qpp::randidx (
        idx a = std::numeric_limits<idx>::min(),
        idx b = std::numeric_limits<idx>::max() ) [inline]
```

Generates a random index (idx) uniformly distributed in the interval [a, b].

Parameters

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

Returns

Random index (idx) uniformly distributed in the interval [a, b]

6.1.3.135 randket()

```
ket qpp::randket (
idx D = 2) [inline]
```

Generates a random normalized ket (pure state vector)

Parameters

D Dimension of the Hilbert space

Returns

Random normalized ket

6.1.3.136 randkraus()

```
std::vector<cmat> qpp::randkraus (
    idx N,
    idx D = 2 ) [inline]
```

Generates a set of random Kraus operators.

Note

The set of Kraus operators satisfy the closure condition $\sum_i K_i^\dagger K_i = I$

Parameters

N	Number of Kraus operators
D	Dimension of the Hilbert space

Returns

Set of N Kraus operators satisfying the closure condition

Generates a random matrix with entries normally distributed in N(mean, sigma)

If complex, then both real and imaginary parts are normally distributed in N(mean, sigma)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries normally distributed in N(0,2)
dmat mat = randn<dmat>(3, 3, 0, 2);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Returns

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd, 
// with entries (both real and imaginary) normally distributed in N(0,2) cmat mat = randn<cmat>(3, 3, 0, 2);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Returns

Random complex matrix

Generates a random real number (double) normally distributed in N(mean, sigma)

Parameters

mean	Mean
sigma	Standard deviation

Returns

Random real number normally distributed in N(mean, sigma)

6.1.3.141 randperm()

```
std::vector<idx> qpp::randperm (
    idx N ) [inline]
```

Generates a random uniformly distributed permutation.

Uses Knuth shuffle method (as implemented by std::shuffle), so that all permutations are equally probable

Parameters

```
N Size of the permutation
```

Returns

Random permutation of size N

6.1.3.142 randprime()

```
bigint qpp::randprime (
          bigint a,
          bigint b,
          idx N = 1000 ) [inline]
```

Generates a random big prime uniformly distributed in the interval [a, b].

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it
N	Maximum number of candidates

Random big integer uniformly distributed in the interval [a, b]

6.1.3.143 randprob()

```
\label{eq:std::vector} $$ \std::vector<double> qpp::randprob ( idx N) [inline]
```

Generates a random probability vector uniformly distributed over the probability simplex.

Parameters

N Size of the probability vector

Returns

Random probability vector

6.1.3.144 randrho()

```
cmat qpp::randrho (
    idx D = 2 ) [inline]
```

Generates a random density matrix.

Parameters

D Dimension of the Hilbert space

Returns

Random density matrix

6.1.3.145 randU()

```
cmat qpp::randU (
    idx D = 2) [inline]
```

Generates a random unitary matrix.

D Dimension of the Hilbert space

Returns

Random unitary

6.1.3.146 randV()

Generates a random isometry matrix.

Parameters

Din	Size of the input Hilbert space
Dout	Size of the output Hilbert space

Returns

Random isometry matrix

```
6.1.3.147 renyi() [1/2]
```

Renyi- α entropy of the density matrix ${\it A}$, for $\alpha \geq 0$.

Note

When $\alpha \to 1$ the Renyi entropy converges to the von-Neumann entropy, with the logarithm in base 2

Α	Eigen expression
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

Renyi- α entropy, with the logarithm in base 2

Renyi- α entropy of the probability distribution *prob*, for $\alpha \geq 0$.

Note

When $\alpha \to 1$ the Renyi entropy converges to the Shannon entropy, with the logarithm in base 2

Parameters

prob	Real probability vector
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

Returns

Renyi- α entropy, with the logarithm in base 2

6.1.3.149 reshape()

Reshape.

Uses column-major order when reshaping (same as MATLAB)

Α	Eigen expression
rows	Number of rows of the reshaped matrix
cols	Number of columns of the reshaped matrix

Reshaped matrix with rows rows and cols columns, as a dynamic matrix over the same scalar field as A

6.1.3.150 rho2bloch()

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

See also

qpp::bloch2rho()

Note

It is implicitly assumed that the density matrix is Hermitian

Parameters

A Eigen expression

Returns

3-dimensional Bloch vector

6.1.3.151 rho2pure()

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

Note

No purity check is done, the input state A must have rank one, otherwise the function returns the first non-zero eigenvector of A

Parameters

A Eigen expression, assumed to be proportional to a projector onto a pure state, i.e. A is assumed to have rank one

The unique non-zero eigenvector of A (up to a phase), as a dynamic column vector over the same scalar field as A

6.1.3.152 save()

Saves Eigen expression to a binary file (internal format) in double precision.

See also

qpp::load()

Parameters

Α	Eigen expression
fname	Output file name

6.1.3.153 saveMATLAB() [1/2]

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

qpp::loadMATLAB()

Template Parameters

Complex Eigen type

Α	Eigen expression over the complex field
---	---

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be saved
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details

6.1.3.154 saveMATLAB() [2/2]

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

qpp::loadMATLAB()

Template Parameters

Npn-complex	Eigen type
-------------	------------

Parameters

Α	Non-complex Eigen expression	
mat_file	MATALB .mat file	
var_name	Variable name in the .mat file representing the matrix to be saved	
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details	

6.1.3.155 schatten()

Schatten matrix norm.

Α	Eigen expression
p	Real number, greater or equal to 1, use qpp::infty for $p=\infty$

Schatten-p matrix norm of A

Schmidt basis on Alice side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix \boldsymbol{U} whose columns represent the Schmidt basis vectors on Alice side.

Schmidt basis on Alice side.

idx d = 2)

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix U whose columns represent the Schmidt basis vectors on Alice side.

6.1.3.158 schmidtB() [1/2] template<typename Derived > cmat qpp::schmidtB (

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & dims )
```

Schmidt basis on Bob side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

Schmidt basis on Bob side.

idx d = 2)

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.161 schmidtcoeffs() [2/2]

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.162 schmidtprobs() [1/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.3.163 schmidtprobs() [2/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.3.164 sigma()

Standard deviation.

prob	Real probability vector representing the probability distribution of X
X	Real random variable values represented by an STL-like container

Returns

Standard deviation of X

6.1.3.165 sinm()

Matrix sin.

Parameters

A Eigen expression

Returns

Matrix sine of A

6.1.3.166 spectralpowm()

Matrix power.

See also

qpp::powm()

Uses the spectral decomposition of \emph{A} to compute the matrix power. By convention $\emph{A}^0 = \emph{I}$.

Α	Eigen expression
Z	Complex number

Matrix power A^z

6.1.3.167 sqrtm()

Matrix square root.

Parameters

```
A Eigen expression
```

Returns

Matrix square root of A

6.1.3.168 sum() [1/3]

Element-wise sum of A.

Parameters

```
A Eigen expression
```

Returns

Element-wise sum of A, as a scalar over the same scalar field as A

6.1.3.169 sum() [2/3]

Element-wise sum of an STL-like range.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Element-wise sum of the range, as a scalar over the same scalar field as the range

Element-wise sum of the elements of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Element-wise sum of the elements of the container, as a scalar over the same scalar field as the container

6.1.3.171 super2choi()

Converts superoperator matrix to Choi matrix.

See also

qpp::choi2super()

Parameters

A Superoperator matrix

Returns

Choi matrix

6.1.3.172 svals()

Singular values.

Parameters

A Eigen expression

Returns

Singular values of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.173 svd()

Full singular value decomposition.

Parameters

A Eigen expression

Returns

Tuple of: 1. Left sigular vectors of A, as columns of a complex dynamic matrix, 2. Singular values of A, ordered in decreasing order, as a real dynamic column vector, and 3. Right singular vectors of A, as columns of a complex dynamic matrix

6.1.3.174 svdU()

Left singular vectors.

Parameters

```
A Eigen expression
```

Returns

Complex dynamic matrix, whose columns are the left singular vectors of A

6.1.3.175 svdV()

Right singular vectors.

Parameters

```
A Eigen expression
```

Returns

Complex dynamic matrix, whose columns are the right singular vectors of A

6.1.3.176 syspermute() [1/2]

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Parameters

Α	Eigen expression
perm	Permutation
dims	Dimensions of the multi-partite system

Returns

Permuted system, as a dynamic matrix over the same scalar field as A

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Parameters

Α	Eigen expression	
perm	Permutation	
d	Subsystem dimensions	

Returns

Permuted system, as a dynamic matrix over the same scalar field as A

6.1.3.178 TFQ()

Inverse (adjoint) qudit quantum Fourier transform.

Parameters

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Inverse (adjoint) qudit quantum Fourier transform applied on A

6.1.3.179 trace()

Trace.

Parameters

```
A Eigen expression
```

Returns

Trace of A, as a scalar over the same scalar field as A

6.1.3.180 transpose()

Transpose.

Parameters

```
A Eigen expression
```

Returns

Transpose of A, as a dynamic matrix over the same scalar field as A

```
6.1.3.181 tsallis() [1/2] template<typename Derived > double qpp::tsallis ( const Eigen::MatrixBase< Derived > & A, double q)
```

Tsallis- q entropy of the density matrix A, for $q \ge 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the von-Neumann entropy, with the logarithm in base e

Parameters

Α	Eigen expression
q	Non-negative real number

Returns

Tsallis- q entropy

Tsallis- q entropy of the probability distribution *prob*, for $q \ge 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the Shannon entropy, with the logarithm in base e

Parameters

prob	Real probability vector
q	Non-negative real number

Returns

Tsallis- q entropy

6.1.3.183 uniform()

```
std::vector<double> qpp::uniform (
    idx N ) [inline]
```

Uniform probability distribution vector.

Parameters

N Size of the alphabet

Returns

Real vector consisting of a uniform distribution of size N

6.1.3.184 var()

Variance.

Parameters

prob	Real probability vector representing the probability distribution of X
Χ	Real random variable values represented by an STL-like container

Returns

Variance of X

6.1.3.185 x2contfrac()

Simple continued fraction expansion.

See also

```
qpp::contfrac2x()
```

Parameters

Χ	Real number
Ν	Maximum number of terms in the expansion
cut	Stop the expansion when the next term is greater than cut

Returns

Integer vector containing the simple continued fraction expansion of x. If there are M less than N terms in the expansion, a shorter vector with M components is returned.

6.1.4 Variable Documentation

6.1.4.1 chop

```
constexpr double qpp::chop = 1e-10
```

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

6.1.4.2 ee

```
constexpr double qpp::ee = 2.718281828459045235360287471352662497
```

Base of natural logarithm, e.

6.1.4.3 eps

```
constexpr double qpp::eps = std::numeric_limits<double>::epsilon()
```

Used to decide whether a number or expression in double precision is zero or not for the purpose of a specific computation.

Example:

```
if(std::abs(x) < qpp::eps) // x is zero</pre>
```

6.1.4.4 idx_infty

```
const idx qpp::idx_infty = static_cast<idx>(-1)
```

Used to denote the largest unsigned index.

6.1.4.5 infty

```
constexpr double qpp::infty = std::numeric_limits<double>::max()
```

Used to denote infinity in double precision.

6.1.4.6 maxn

```
constexpr idx qpp::maxn = 64
```

Maximum number of allowed qubits/qudits (subsystems)

Used internally to allocate arrays on the stack (for performance reasons):

6.1.4.7 pi

```
constexpr double qpp::pi = 3.141592653589793238462643383279502884
```

 π

6.2 qpp::exception Namespace Reference

Quantum++ exception hierarchy namespace.

Classes

• class CustomException

Custom exception.

· class DimsInvalid

Invalid dimension(s) exception.

· class DimsMismatchCvector

Dimension(s) mismatch column vector size exception.

• class DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

· class DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

· class DimsMismatchVector

Dimension(s) mismatch vector size exception.

class DimsNotEqual

Dimensions not equal exception.

· class Duplicates

System (e.g. std::vector) has duplicates exception.

class Exception

Base class for generating Quantum++ custom exceptions.

class InvalidIterator

Invalid iterator.

• class MatrixMismatchSubsys

Matrix mismatch subsystems exception.

• class MatrixNotCvector

Matrix is not a column vector exception.

class MatrixNotRvector

Matrix is not a row vector exception.

class MatrixNotSquare

Matrix is not square exception.

· class MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

class MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

· class MatrixNotSquareNorVector

Matrix is not square nor vector exception.

· class MatrixNotVector

Matrix is not a vector exception.

class NoCodeword

Codeword does not exist exception.

· class NotBipartite

Not bi-partite exception.

· class NotImplemented

Code not yet implemented.

class NotQubitCvector

Column vector is not 2 x 1 exception.

class NotQubitMatrix

Matrix is not 2 x 2 exception.

· class NotQubitRvector

Row vector is not 1 x 2 exception.

class NotQubitSubsys

Subsystems are not qubits exception.

class NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

class OutOfRange

Argument out of range exception.

class PermInvalid

Invalid permutation exception.

· class PermMismatchDims

Permutation mismatch dimensions exception.

class QuditAlreadyMeasured

Qudit was already measured exception.

· class SizeMismatch

Size mismatch exception.

• class SubsysMismatchDims

Subsystems mismatch dimensions exception.

class TypeMismatch

Type mismatch exception.

class UndefinedType

Not defined for this type exception.

• class Unknown

Unknown exception.

class ZeroSize

Object has zero size exception.

6.2.1 Detailed Description

Quantum++ exception hierarchy namespace.

6.3 qpp::experimental Namespace Reference

Experimental/test functions/classes, do not use or modify.

6.3.1 Detailed Description

Experimental/test functions/classes, do not use or modify.

6.4 qpp::internal Namespace Reference

Internal utility functions, do not use them directly or modify them.

Classes

- struct Display Impl
- · class IOManipEigen
- · class IOManipPointer
- · class IOManipRange
- · class Singleton

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Functions

- void n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- $\bullet \ \ \text{template}{<} \text{typename Derived} >$

bool check_square_mat (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ \mathsf{template} \mathord{<} \mathsf{typename} \ \mathsf{Derived} >$

bool bool check_vector (const Eigen::MatrixBase Derived > &A)

• template<typename Derived >

bool check_rvector (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

bool check_cvector (const Eigen::MatrixBase< Derived > &A)

• template<typename T >

bool check_nonzero_size (const T &x) noexcept

- template<typename T1 , typename T2 >

bool check_matching_sizes (const T1 &lhs, const T2 &rhs) noexcept

- bool check_dims (const std::vector< idx > &dims)
- template<typename Derived >

 $bool\ check_dims_match_mat\ (const\ std::vector < idx > \&dims,\ const\ Eigen::MatrixBase < Derived > \&A)$

• template<typename Derived >

bool check_dims_match_cvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool check dims match rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- bool check_eq_dims (const std::vector< idx > &dims, idx dim) noexcept
- bool check_no_duplicates (std::vector< idx > v)
- bool check_subsys_match_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)

```
    template < typename Derived >
        bool check_qubit_matrix (const Eigen::MatrixBase < Derived > &A) noexcept
```

• template<typename Derived >

bool check_qubit_cvector (const Eigen::MatrixBase< Derived > &A) noexcept

template<typename Derived >
 bool check_qubit_rvector (const Eigen::MatrixBase< Derived > &A) noexcept

template<typename Derived >
 bool check_qubit_vector (const Eigen::MatrixBase< Derived > &A) noexcept

bool check_perm (const std::vector< idx > &perm)

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > kron2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::
 MatrixBase< Derived2 > &B)

template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > dirsum2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen
 ::MatrixBase< Derived2 > &B)

template<typename T > void variadic_vector_emplace (std::vector< T > &)

- $\begin{tabular}{ll} & \textbf{template}$<&typename T$, typename First , typename... Args>&void variadic_vector_emplace (std::vector< T>&v, First &&first, Args &&... args) \\ \end{tabular}$
- idx get num subsys (idx D, idx d)
- idx get_dim_subsys (idx sz, idx N)

6.4.1 Detailed Description

Internal utility functions, do not use them directly or modify them.

6.4.2 Function Documentation

6.4.2.1 check_cvector()

6.4.2.2 check_dims()

```
bool qpp::internal::check_dims (  const \ std::vector < \ idx \ > \ \& \ dims \ ) \quad [inline]
```

6.4.2.3 check_dims_match_cvect()

6.4.2.4 check_dims_match_mat()

6.4.2.5 check_dims_match_rvect()

6.4.2.6 check_eq_dims()

6.4.2.7 check_matching_sizes()

6.4.2.8 check_no_duplicates()

```
bool qpp::internal::check_no_duplicates ( {\tt std::vector} < {\tt idx} \, > \, v \; ) \quad [{\tt inline}]
```

```
6.4.2.9 check_nonzero_size()
template<typename T >
bool qpp::internal::check_nonzero_size (
            const T & x ) [noexcept]
6.4.2.10 check_perm()
bool qpp::internal::check_perm (
            const std::vector< idx > & perm ) [inline]
6.4.2.11 check_qubit_cvector()
template<typename Derived >
bool qpp::internal::check_qubit_cvector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.12 check_qubit_matrix()
template<typename Derived >
bool qpp::internal::check_qubit_matrix (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.13 check_qubit_rvector()
template<typename Derived >
bool qpp::internal::check_qubit_rvector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.14 check_qubit_vector()
template<typename Derived >
bool qpp::internal::check_qubit_vector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
```

```
6.4.2.15 check_rvector()
```

```
template<typename Derived >
bool qpp::internal::check_rvector (
            const Eigen::MatrixBase< Derived > & A )
6.4.2.16 check_square_mat()
template<typename Derived >
bool qpp::internal::check_square_mat (
            const Eigen::MatrixBase< Derived > & A )
6.4.2.17 check_subsys_match_dims()
bool qpp::internal::check_subsys_match_dims (
            const std::vector< idx > & subsys,
            const std::vector< idx > & dims ) [inline]
6.4.2.18 check_vector()
template<typename Derived >
bool qpp::internal::check_vector (
            const Eigen::MatrixBase< Derived > & A )
6.4.2.19 dirsum2()
template<typename Derived1 , typename Derived2 >
dyn_mat<typename Derived1::Scalar> qpp::internal::dirsum2 (
            const Eigen::MatrixBase< Derived1 > & A,
            const Eigen::MatrixBase< Derived2 > & B )
6.4.2.20 get_dim_subsys()
idx qpp::internal::get_dim_subsys (
            idx sz,
             idx N ) [inline]
```

6.4.2.21 get_num_subsys()

```
idx qpp::internal::get_num_subsys (
            idx D,
             idx d ) [inline]
6.4.2.22 kron2()
template<typename Derived1 , typename Derived2 >
dyn_mat<typename Derived1::Scalar> qpp::internal::kron2 (
            const Eigen::MatrixBase< Derived1 > & A,
             const Eigen::MatrixBase< Derived2 > & B )
6.4.2.23 multiidx2n()
idx qpp::internal::multiidx2n (
             const idx *const midx,
             idx numdims,
             const idx *const dims ) [inline], [noexcept]
6.4.2.24 n2multiidx()
void qpp::internal::n2multiidx (
             idx n,
             idx numdims,
             const idx *const dims,
             idx * result ) [inline], [noexcept]
6.4.2.25 variadic_vector_emplace() [1/2]
template<typename T >
void qpp::internal::variadic_vector_emplace (
            std::vector< T > & )
6.4.2.26 variadic_vector_emplace() [2/2]
template<typename T , typename First , typename... Args>
void qpp::internal::variadic_vector_emplace (
             std::vector< T > & v,
             First && first,
             Args &&... args )
```

6.5 qpp::literals Namespace Reference

Functions

```
• constexpr cplx operator"" _i (unsigned long long int x) noexcept \textit{User-defined literal for complex } i = \sqrt{-1} \textit{ (integer overload)}
```

```
template<char... Bits>
ket operator"" _ket ()
```

Multi-partite qubit ket user-defined literal.

template<char... Bits> bra operator"" _bra ()

Multi-partite qubit bra user-defined literal.

template<char... Bits> cmat operator"" _prj ()

Multi-partite qubit projector user-defined literal.

6.5.1 Function Documentation

```
6.5.1.1 operator"""_bra()

template<char... Bits>
bra qpp::literals::operator"" _bra ( )
```

Multi-partite qubit bra user-defined literal.

See also

```
qpp::mket() and qpp::adjoint()
```

Constructs the multi-partite qubit bra $\langle \mathrm{Bits}|$

Template Parameters

```
Bits String of binary numbers representing the qubit bra
```

Returns

Multi-partite qubit bra, as a complex dynamic row vector

User-defined literal for complex $i = \sqrt{-1}$ (integer overload)

Example:

```
cplx z = 4_i; // type of z is std::complex<double>
```

6.5.1.3 operator""" _ket()

```
template<char... Bits>
ket qpp::literals::operator"" _ket ( )
```

Multi-partite qubit ket user-defined literal.

See also

qpp::mket()

Constructs the multi-partite qubit ket $|Bits\rangle$

Template Parameters

Bits	String of binary numbers representing the qubit ket
------	---

Returns

Multi-partite qubit ket, as a complex dynamic column vector

6.5.1.4 operator""" _prj()

```
template<char... Bits>
cmat qpp::literals::operator"" _prj ( )
```

Multi-partite qubit projector user-defined literal.

See also

qpp::mprj()

Constructs the multi-partite qubit projector $|\mathrm{Bits}\rangle\langle\mathrm{Bits}|$ (in the computational basis)

Template Parameters

Bits String of binary numbers representing the qubit state to project on

\mathbf{L}	ΔT	 rn	c

Multi-partite qubit projector, as a complex dynamic matrix

Chapter 7

Class Documentation

7.1 qpp::Bit_circuit Class Reference


Classical reversible circuit simulator.

#include <classes/reversible.h>

Inheritance diagram for qpp::Bit_circuit:



Collaboration diagram for qpp::Bit_circuit:



Classes

struct Gate_count

Public Member Functions

- Bit_circuit (const Dynamic_bitset &dynamic_bitset)
 - Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.
- Bit_circuit & X (idx pos)

Bit flip.

Bit_circuit & NOT (idx pos)

Bit flip

• Bit_circuit & CNOT (const std::vector< idx > &pos)

Controlled-NOT.

• Bit_circuit & TOF (const std::vector< idx > &pos)

Toffoli gate.

Bit_circuit & SWAP (const std::vector < idx > &pos)

Swap bits.

• Bit_circuit & FRED (const std::vector< idx > &pos)

Fredkin gate (Controlled-SWAP)

• Bit_circuit & reset () noexcept

Reset the circuit all zero, clear all gates.

Dynamic_bitset (idx N)

Inherited constructor.

Public Attributes

struct qpp::Bit_circuit::Gate_count gate_count
 Gate counters.

Additional Inherited Members

7.1.1 Detailed Description

Classical reversible circuit simulator.

7.1.2 Constructor & Destructor Documentation

7.1.2.1 Bit_circuit()

Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.

Parameters

7.1.3 Member Function Documentation

7.1.3.1 CNOT()

Controlled-NOT.

Parameters

```
pos Bit position in the circuit
```

Returns

Reference to the current instance

7.1.3.2 Dynamic_bitset()

```
qpp::Dynamic_bitset::Dynamic_bitset [inline], [explicit]
```

Inherited constructor.

7.1.3.3 FRED()

Fredkin gate (Controlled-SWAP)

Parameters

pos Bit positions in the circuit, in the order control-target-target

Returns

Reference to the current instance

7.1.3.4 NOT()

```
Bit_circuit& qpp::Bit_circuit::NOT (
        idx pos ) [inline]
```

Bit flip.

See also

qpp::Bit_circuit::X()

Parameters

pos Bit position in the circuit

Returns

Reference to the current instance

7.1.3.5 reset()

```
Bit_circuit& qpp::Bit_circuit::reset ( ) [inline], [noexcept]
```

Reset the circuit all zero, clear all gates.

Returns

Reference to the current instance

7.1.3.6 SWAP()

Swap bits.

Parameters

pos Bit positions in the circuit

Returns

Reference to the current instance

7.1.3.7 TOF()

Toffoli gate.

Parameters

pos | Bit positions in the circuit, in the order control-control-target

Returns

Reference to the current instance

7.1.3.8 X()

```
Bit_circuit& qpp::Bit_circuit::X (
        idx pos ) [inline]
```

Bit flip.

See also

qpp::Bit_circuit::NOT()

Parameters

pos Bit position in the circuit

Returns

Reference to the current instance

7.1.4 Member Data Documentation

7.1.4.1 gate_count

```
struct qpp::Bit_circuit::Gate_count qpp::Bit_circuit::gate_count
```

Gate counters.

The documentation for this class was generated from the following file:


• classes/reversible.h

7.2 qpp::Codes Class Reference


const Singleton class that defines quantum error correcting codes

```
#include <classes/codes.h>
```

Inheritance diagram for qpp::Codes:



Collaboration diagram for qpp::Codes:



Public Types

• enum Type { Type::FIVE_QUBIT = 1, Type::SEVEN_QUBIT_STEANE, Type::NINE_QUBIT_SHOR }

Code types, add more codes here if needed.

Public Member Functions

ket codeword (Type type, idx i) const
 Returns the codeword of the specified code type.

Private Member Functions

• Codes ()

Default constructor.

∼Codes ()=default

Default destructor.

Friends

class internal::Singleton < const Codes >

Additional Inherited Members

7.2.1 Detailed Description

const Singleton class that defines quantum error correcting codes

7.2.2 Member Enumeration Documentation

7.2.2.1 Type

```
enum qpp::Codes::Type [strong]
```

Code types, add more codes here if needed.

See also

```
qpp::Codes::codeword()
```

Enumerator

FIVE_QUBIT	[[5,1,3]] qubit code
SEVEN_QUBIT_STEANE	[[7,1,3]] Steane qubit code
NINE_QUBIT_SHOR	[[9,1,3]] Shor qubit code

7.2.3 Constructor & Destructor Documentation

7.2.3.1 Codes()

```
qpp::Codes::Codes ( ) [inline], [private]
```

Default constructor.

7.2.3.2 ∼Codes()

```
qpp::Codes::~Codes ( ) [private], [default]
```

Default destructor.

7.2.4 Member Function Documentation

7.2.4.1 codeword()

Returns the codeword of the specified code type.

See also

qpp::Codes::Type

Parameters

type	Code type
i	Codeword index

Returns

i-th codeword of the code type

7.2.5 Friends And Related Function Documentation

7.2.5.1 internal::Singleton < const Codes >

```
friend class internal::Singleton< const Codes > [friend]
```

The documentation for this class was generated from the following file:

classes/codes.h

7.3 qpp::exception::CustomException Class Reference


Custom exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::CustomException:



Collaboration diagram for qpp::exception::CustomException:



Public Member Functions

· CustomException (const std::string &where, const std::string &what)

Private Member Functions

std::string type_description () const override
 Exception type description.

Private Attributes

std::string what_{{}}

7.3.1 Detailed Description

Custom exception.

Custom exception, the user must provide a custom message

7.3.2 Constructor & Destructor Documentation

7.3.2.1 CustomException()

7.3.3 Member Function Documentation

7.3.3.1 type_description()

```
std::string qpp::exception::CustomException::type_description ( ) const [inline], [override],
[private], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

7.3.4 Member Data Documentation

7.3.4.1 what_

```
std::string qpp::exception::CustomException::what_ {} [private]
```

The documentation for this class was generated from the following file:


· classes/exception.h

7.4 qpp::exception::DimsInvalid Class Reference

Invalid dimension(s) exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsInvalid:



Collaboration diagram for qpp::exception::DimsInvalid:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.4.1 Detailed Description

Invalid dimension(s) exception.

std::vector<idx> of dimensions has zero size or contains zeros

7.4.2 Member Function Documentation

7.4.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.4.2.2 type_description()

std::string qpp::exception::DimsInvalid::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.5 qpp::exception::DimsMismatchCvector Class Reference


Dimension(s) mismatch column vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchCvector:



Collaboration diagram for qpp::exception::DimsMismatchCvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.5.1 Detailed Description

Dimension(s) mismatch column vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a column vector)

7.5.2 Member Function Documentation

7.5.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred
--

7.5.2.2 type_description()

std::string qpp::exception::DimsMismatchCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.6 qpp::exception::DimsMismatchMatrix Class Reference


Dimension(s) mismatch matrix size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchMatrix:



Collaboration diagram for qpp::exception::DimsMismatchMatrix:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.6.1 Detailed Description

Dimension(s) mismatch matrix size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of rows of the Eigen::Matrix (assumed to be a square matrix)

7.6.2 Member Function Documentation

7.6.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred
--

7.6.2.2 type_description()

```
std::string qpp::exception::DimsMismatchMatrix::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

7.7 qpp::exception::DimsMismatchRvector Class Reference


Dimension(s) mismatch row vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchRvector:



Collaboration diagram for qpp::exception::DimsMismatchRvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.7.1 Detailed Description

Dimension(s) mismatch row vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row vector)

7.7.2 Member Function Documentation

7.7.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

Text representing where the exception of	d
--	---

7.7.2.2 type_description()

std::string qpp::exception::DimsMismatchRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

7.8 qpp::exception::DimsMismatchVector Class Reference

Dimension(s) mismatch vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchVector:



Collaboration diagram for qpp::exception::DimsMismatchVector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.8.1 Detailed Description

Dimension(s) mismatch vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row/column vector)

7.8.2 Member Function Documentation

7.8.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
******	Toxt representing where the exception eccurred

7.8.2.2 type_description()

```
std::string qpp::exception::DimsMismatchVector::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.9 qpp::exception::DimsNotEqual Class Reference


Dimensions not equal exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsNotEqual:



Collaboration diagram for qpp::exception::DimsNotEqual:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.9.1 Detailed Description

Dimensions not equal exception.

Local/global dimensions are not equal

7.9.2 Member Function Documentation

7.9.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.9.2.2 type_description()

std::string qpp::exception::DimsNotEqual::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

7.10 qpp::internal::Display_Impl_ Struct Reference

```
#include <internal/util.h>
```

Inheritance diagram for qpp::internal::Display_Impl_:



Public Member Functions

template<typename T >
 std::ostream & display_impl_ (const T &A, std::ostream &os, double chop=qpp::chop) const

7.10.1 Member Function Documentation

7.10.1.1 display_impl_()

The documentation for this struct was generated from the following file:


• internal/util.h

7.11 qpp::exception::Duplicates Class Reference


System (e.g. std::vector) has duplicates exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Duplicates:



Collaboration diagram for qpp::exception::Duplicates:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.11.1 Detailed Description

System (e.g. std::vector) has duplicates exception.

7.11.2 Member Function Documentation

7.11.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.11.2.2 type_description()

```
std::string qpp::exception::Duplicates::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.12 qpp::Dynamic_bitset Class Reference

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std:bitset < N >)

#include <classes/reversible.h>

Inheritance diagram for qpp::Dynamic_bitset:



Collaboration diagram for qpp::Dynamic_bitset:



Public Types

- using value_type = unsigned int
 Type of the storage elements.
- using storage_type = std::vector< value_type >
 Type of the storage.

Public Member Functions

• Dynamic bitset (idx N)

Constructor, initializes all bits to false (zero)

virtual ~Dynamic bitset ()=default

Default virtual destructor.

const storage_type & data () const

Raw storage space of the bitset.

• idx size () const noexcept

Number of bits stored in the bitset.

• idx storage_size () const noexcept

Size of the underlying storage space (in units of value_type, unsigned int by default)

· idx count () const noexcept

Number of bits set to one in the bitset (Hamming weight)

bool get (idx pos) const noexcept

The value of the bit at position pos.

· bool none () const noexcept

Checks whether none of the bits are set.

• bool all () const noexcept

Checks whether all bits are set.

• bool any () const noexcept

Checks whether any bit is set.

Dynamic_bitset & set (idx pos, bool value=true)

Sets the bit at position pos.

Dynamic_bitset & set () noexcept

Set all bits to true.

• Dynamic bitset & rand (idx pos, double p=0.5)

Sets the bit at position pos according to a Bernoulli(p) distribution.

• Dynamic_bitset & rand (double p=0.5)

Sets all bits according to a Bernoulli(p) distribution.

Dynamic_bitset & reset (idx pos)

Sets the bit at position pos to false.

Dynamic_bitset & reset () noexcept

Sets all bits to false.

Dynamic_bitset & flip (idx pos)

Flips the bit at position pos.

· Dynamic bitset & flip () noexcept

Flips all bits.

• bool operator== (const Dynamic_bitset &rhs) const noexcept

Equality operator.

• bool operator!= (const Dynamic_bitset &rhs) const noexcept

Inequality operator.

• idx operator- (const Dynamic_bitset &rhs) const noexcept

Number of places the two bitsets differ (Hamming distance)

template < class CharT = char, class Traits = std::char_traits < CharT>, class Allocator = std::allocator < CharT>> std::basic_string < CharT, Traits, Allocator > to_string (CharT zero=CharT('0'), CharT one=CharT('1')) const String representation.

Protected Member Functions

- idx index_ (idx pos) const
 Index of the pos bit in the storage space.
- idx offset_ (idx pos) const

Offset of the pos bit in the storage space relative to its index.

Protected Attributes

```
• idx storage_size_
Storage size.
```

idx N

Number of bits.

std::vector< value_type > v_
 Storage space.

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display()* override, displays the bitset bit by bit

7.12.1 Detailed Description

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

7.12.2 Member Typedef Documentation

```
7.12.2.1 storage_type
```

```
using qpp::Dynamic_bitset::storage_type = std::vector<value_type>
```

Type of the storage.

7.12.2.2 value_type

```
using qpp::Dynamic_bitset::value_type = unsigned int
```

Type of the storage elements.

7.12.3 Constructor & Destructor Documentation

7.12.3.1 Dynamic_bitset()

Constructor, initializes all bits to false (zero)

Parameters

N Number of bits in the bitset

```
7.12.3.2 ~Dynamic_bitset()
```

```
virtual qpp::Dynamic_bitset::~Dynamic_bitset ( ) [virtual], [default]
```

Default virtual destructor.

7.12.4 Member Function Documentation

```
7.12.4.1 all()
```

```
bool qpp::Dynamic_bitset::all ( ) const [inline], [noexcept]
```

Checks whether all bits are set.

Returns

True if all of the bits are set

7.12.4.2 any()

```
bool qpp::Dynamic_bitset::any ( ) const [inline], [noexcept]
```

Checks whether any bit is set.

Returns

True if any of the bits is set

7.12.4.3 count()

```
idx qpp::Dynamic_bitset::count ( ) const [inline], [noexcept]
```

Number of bits set to one in the bitset (Hamming weight)

Returns

Hamming weight

7.12.4.4 data()

```
const storage_type& qpp::Dynamic_bitset::data ( ) const [inline]
```

Raw storage space of the bitset.

Returns

Const reference to the underlying storage space

7.12.4.5 display()

qpp::IDisplay::display() override, displays the bitset bit by bit

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.12.4.6 flip() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip (
        idx pos ) [inline]
```

Flips the bit at position pos.

Parameters

pos Position in the bitset

Returns

Reference to the current instance

```
7.12.4.7 flip() [2/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip ( ) [inline], [noexcept]
```

Flips all bits.

Returns

Reference to the current instance

7.12.4.8 get()

```
bool qpp::Dynamic_bitset::get (
          idx pos ) const [inline], [noexcept]
```

The value of the bit at position pos.

Parameters

pos	Position in the bitset
-----	------------------------

Returns

The value of the bit at position pos

7.12.4.9 index_()

Index of the pos bit in the storage space.

Parameters

```
pos Bit location
```

Returns

Index of the pos bit in the storage space

7.12.4.10 none()

```
bool qpp::Dynamic_bitset::none ( ) const [inline], [noexcept]
```

Checks whether none of the bits are set.

Returns

True if none of the bits are set

7.12.4.11 offset_()

Offset of the *pos* bit in the storage space relative to its index.

Parameters

```
pos Bit location
```

Returns

Offset of the pos bit in the storage space relative to its index

7.12.4.12 operator"!=()

Inequality operator.

Parameters

```
rhs Dynamic_bitset against which the inequality is being tested
```

Returns

True if the bitsets are not equal (bit by bit), false otherwise

7.12.4.13 operator-()

Number of places the two bitsets differ (Hamming distance)

Parameters

```
rhs Dynamic_bitset against which the Hamming distance is computed
```

Returns

Hamming distance

7.12.4.14 operator==()

Equality operator.

Parameters

```
rhs Dynamic_bitset against which the equality is being tested
```

Returns

True if the bitsets are equal (bit by bit), false otherwise

7.12.4.15 rand() [1/2]

```
Dynamic_bitset& qpp::Dynamic_bitset::rand (
    idx pos,
    double p = 0.5 ) [inline]
```

Sets the bit at position *pos* according to a Bernoulli(p) distribution.

Parameters

pos	Position in the bitset
р	Probability

Returns

Reference to the current instance

Sets all bits according to a Bernoulli(p) distribution.

Parameters

```
p Probability
```

Returns

Reference to the current instance

Sets the bit at position pos to false.

Parameters

```
pos Position in the bitset
```

Returns

Reference to the current instance

```
7.12.4.18 reset() [2/2]
Dynamic_bitset& qpp::Dynamic_bitset::reset ( ) [inline], [noexcept]
Sets all bits to false.
```

Returns

Reference to the current instance

```
7.12.4.19 set() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::set (
        idx pos,
        bool value = true ) [inline]
```

Sets the bit at position pos.

Parameters

pos	Position in the bitset
value	Bit value

Returns

Reference to the current instance

```
7.12.4.20 set() [2/2]
Dynamic_bitset& qpp::Dynamic_bitset::set ( ) [inline], [noexcept]
```

Set all bits to true.

Returns

Reference to the current instance

```
7.12.4.21 size()
```

```
idx qpp::Dynamic_bitset::size ( ) const [inline], [noexcept]
```

Number of bits stored in the bitset.

Returns

Number of bits stored in the bitset

```
7.12.4.22 storage_size()
```

```
idx qpp::Dynamic_bitset::storage_size ( ) const [inline], [noexcept]
```

Size of the underlying storage space (in units of value_type, unsigned int by default)

Returns

Size of the underlying storage space

7.12.4.23 to_string()

String representation.

Template Parameters

CharT	String character type
Traits	String traits
Allocator	String Allocator

Parameters

	Character representing the zero
one	Character representing the one

Returns

The bitset as a string

7.12.5 Member Data Documentation

```
7.12.5.1 N_
```

```
idx qpp::Dynamic_bitset::N_ [protected]
```

Number of bits.


7.12.5.2 storage_size_

```
idx qpp::Dynamic_bitset::storage_size_ [protected]
```

Storage size.

166	Class Documentation
7.12.5.3 v_	
<pre>std::vector<value_type> qpp::Dynamic_bitset::v_ [protected]</value_type></pre>	
Storage space.	
The documentation for this class was generated from the following file:	
• classes/reversible.h	
7.13 qpp::exception::Exception Class Reference	
Base class for generating Quantum++ custom exceptions.	
<pre>#include <classes exception.h=""></classes></pre>	

Inheritance diagram for qpp::exception::Exception:



Collaboration diagram for qpp::exception::Exception:



Public Member Functions

• Exception (const std::string &where)

Constructs an exception.

- virtual const char * what () const noexcept override

Overrides std::exception::what()

• virtual std::string type_description () const =0

Exception type description.

Private Attributes

- std::string where_
- std::string msg_

7.13.1 Detailed Description

Base class for generating Quantum++ custom exceptions.

Derive from this class if more exceptions are needed, making sure to override qpp::exception::Exception::type_description() in the derived class and to inherit the constructor qpp::exception::Exception::Exception(). Preferably keep your newly defined exception classes in the namespace qpp::exception.

Example:

7.13.2 Constructor & Destructor Documentation

7.13.2.1 Exception()

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.13.3 Member Function Documentation

7.13.3.1 type_description()

```
std::string qpp::exception::Exception::type_description ( ) const [inline], [pure virtual]
```

Exception type description.

Returns

Exception type description

Implemented in qpp::exception::InvalidIterator, qpp::exception::NotImplemented, qpp::exception::CustomException, qpp::exception::Duplicates, qpp::exception::QuditAlreadyMeasured, qpp::exception::UndefinedType, qpp::exception::SizeMismatch, qpp::exception::TypeMismatch, qpp::exception::OutOfRange, qpp::exception::NotOdeword, qpp::exception::NotBipartite, qpp::exception::NotQubitSubsys, qpp::exception::NotQubitVector, qpp::exception::NotQubitRvector, qpp::exception::NotQubitCvector qpp::exception::NotQubitMatrix, qpp::exception::PermMismatchDims, qpp::exception::PermInvalid, qpp::exception::SubsysMismatchEqpp::exception::DimsMismatchVector, qpp::exception::DimsMismatchCvector, qpp::exception::DimsMismatchMatrix, qpp::exception::DimsNotEqual, qpp::exception::DimsInvalid, qpp::exception::MatrixMismatchSu qpp::exception::MatrixNotSquareNorVector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::Unknown.

7.13.3.2 what()

virtual const char* qpp::exception::Exception::what () const [inline], [override], [virtual],
[noexcept]

Overrides std::exception::what()

Returns

Exception description

7.13.4 Member Data Documentation

```
7.13.4.1 msg_
```

std::string qpp::exception::Exception::msg_ [mutable], [private]

7.13.4.2 where_

std::string qpp::exception::Exception::where_ [private]

The documentation for this class was generated from the following file:

· classes/exception.h

7.14 qpp::Bit_circuit::Gate_count Struct Reference

```
#include <classes/reversible.h>
```

Public Attributes

- idx NOT = 0
- idx & X = NOT
- idx CNOT = 0
- idx SWAP = 0
- idx FRED = 0
- idx TOF = 0

7.14.1 Member Data Documentation

7.14.1.1 CNOT

```
idx qpp::Bit_circuit::Gate_count::CNOT = 0
```

7.14.1.2 FRED

```
idx qpp::Bit_circuit::Gate_count::FRED = 0
```

7.14.1.3 NOT

```
idx qpp::Bit_circuit::Gate_count::NOT = 0
```

7.14.1.4 SWAP

```
idx qpp::Bit_circuit::Gate_count::SWAP = 0
```

7.14.1.5 TOF

```
idx qpp::Bit_circuit::Gate_count::TOF = 0
```

7.14.1.6 X

```
idx& qpp::Bit_circuit::Gate_count::X = NOT
```

The documentation for this struct was generated from the following file:

• classes/reversible.h

7.15 qpp::Gates Class Reference


const Singleton class that implements most commonly used gates

#include <classes/gates.h>

Inheritance diagram for qpp::Gates:



Collaboration diagram for qpp::Gates:



Public Member Functions

- cmat Rn (double theta, const std::vector< double > &n) const
 Qubit rotation of theta about the 3-dimensional real (unit) vector n.
- cmat RX (double theta) const

Qubit rotation of theta about the X axis.

• cmat RY (double theta) const

Qubit rotation of theta about the Y axis.

cmat RZ (double theta) const

Qubit rotation of theta about the Z axis.

• cmat Zd (idx D=2) const

Generalized Z gate for qudits.

```
• cmat SWAPd (idx D=2) const
          SWAP gate for qudits.
    • cmat Fd (idx D=2) const
          Quantum Fourier transform gate for qudits.

    cmat MODMUL (idx a, idx N, idx n) const

          Modular multiplication gate for qubits Implements |x\rangle \longrightarrow |ax \bmod N\rangle.

    cmat Xd (idx D=2) const

          Generalized X gate for qudits.
    • template<typename Derived = Eigen::MatrixXcd>
      Derived Id (idx D=2) const
          Identity gate.

    template<typename Derived >

      dyn mat< typename Derived::Scalar > CTRL (const Eigen::MatrixBase< Derived > &A, const std::vector<
      idx > &ctrl, const std::vector < idx > &target, idx n, idx d=2) const
          Generates the multi-partite multiple-controlled-A gate in matrix form.

    template<typename Derived >

      dyn mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
      std::vector < idx > &dims) const
          Expands out.

    template<typename Derived >

      dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
      std::initializer list< idx > &dims) const
          Expands out.

    template<typename Derived >

      dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, idx n,
      idx d=2) const
          Expands out.
    • std::string get_name (const cmat &U) const
          Get the name of the most common qubit gates.
Public Attributes
    cmat Id2 {cmat::Identity(2, 2)}
          Identity gate.

    cmat H {cmat::Zero(2, 2)}

          Hadamard gate.
    cmat X {cmat::Zero(2, 2)}
          Pauli Sigma-X gate.

    cmat Y {cmat::Zero(2, 2)}

          Pauli Sigma-Y gate.

    cmat Z {cmat::Zero(2, 2)}

          Pauli Sigma-Z gate.

    cmat S {cmat::Zero(2, 2)}

          S gate.

    cmat T {cmat::Zero(2, 2)}

          T gate.

    cmat CNOT {cmat::Identity(4, 4)}

          Controlled-NOT control target gate.

    cmat CZ {cmat::Identity(4, 4)}

          Controlled-Phase gate.

    cmat CNOTba {cmat::Zero(4, 4)}
```

```
Controlled-NOT target->control gate.
```

• cmat SWAP {cmat::Identity(4, 4)}

SWAP gate.

• cmat TOF {cmat::ldentity(8, 8)}

Toffoli gate.

• cmat FRED {cmat::ldentity(8, 8)}

Fredkin gate.

Private Member Functions

• Gates ()

Initializes the gates.

∼Gates ()=default

Default destructor.

Friends

class internal::Singleton < const Gates >

Additional Inherited Members

7.15.1 Detailed Description

const Singleton class that implements most commonly used gates

7.15.2 Constructor & Destructor Documentation

```
7.15.2.1 Gates()
```

```
qpp::Gates::Gates ( ) [inline], [private]
```

Initializes the gates.

7.15.2.2 \sim Gates()

```
qpp::Gates::\sim Gates ( ) [private], [default]
```

Default destructor.

7.15.3 Member Function Documentation

7.15.3.1 CTRL()

Generates the multi-partite multiple-controlled-A gate in matrix form.

See also

```
qpp::applyCTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
n	Total number of subsystems
d	Subsystem dimensions

Returns

CTRL-A gate, as a matrix over the same scalar field as A

7.15.3.2 expandout() [1/3]

Expands out.

See also

```
qpp::kron()
```

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

	Α	Eigen expression
	pos	Position
ĺ	dims	Dimensions of the multi-partite system

Returns

Tensor product $I\otimes\cdots\otimes I\otimes A\otimes I\otimes\cdots\otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

```
7.15.3.3 expandout() [2/3]
```

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Note

The std::initializer_list overload exists because otherwise, in the degenerate case when *dims* has only one element, the one element list is implicitly converted to the element's underlying type, i.e. qpp::idx, which has the net effect of picking the wrong (non-vector) qpp::expandout() overload

Parameters

Α	Eigen expression
pos	Position
dims	Dimensions of the multi-partite system

Returns

Tensor product $I\otimes\cdots\otimes I\otimes A\otimes I\otimes\cdots\otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.15.3.4 expandout() [3/3]

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

Α	Eigen expression
pos	Position
n	Number of subsystems
d	Subsystem dimensions

Returns

Tensor product $I \otimes \cdots \otimes I \otimes A \otimes I \otimes \cdots \otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.15.3.5 Fd()

```
cmat qpp::Gates::Fd (
    idx D = 2 ) const [inline]
```

Quantum Fourier transform gate for qudits.

Note

Defined as
$$F = \sum_{j,k=0}^{D-1} \exp(2\pi \mathrm{i} jk/D) |j\rangle\langle k|$$

Parameters

D Dimension of the Hilbert space

Returns

Fourier transform gate for qudits

7.15.3.6 get_name()

Get the name of the most common qubit gates.

Note

Assumes that the gate U is represented by a square matrix. If not, returns the empty string

Parameters

U | Complex matrix representing the quantum gate

Returns

The name of the gate (if any), otherwise the empty string

7.15.3.7 ld()

```
template<typename Derived = Eigen::MatrixXcd>
Derived qpp::Gates::Id (
    idx D = 2 ) const [inline]
```

Identity gate.

Note

Can change the return type from complex matrix (default) by explicitly specifying the template parameter

Parameters

D Dimension of the Hilbert space

Returns

Identity gate on a Hilbert space of dimension D

7.15.3.8 MODMUL()

```
cmat qpp::Gates::MODMUL (
    idx a,
```

```
idx N, idx n) const [inline]
```

Modular multiplication gate for qubits Implements $|x\rangle \longrightarrow |ax \bmod N\rangle$.

Note

For the gate to be unitary, *a* and *N* should be co-prime. The function does not check co-primality in release versions!

The number of qubits required to implement the gate should satisfy $n \geq \lceil \log_2(N) \rceil$

Parameters

а	Positive integer less than N
Ν	Positive integer
n	Number of qubits required for implementing the gate

Returns

Modular multiplication gate

7.15.3.9 Rn()

Qubit rotation of *theta* about the 3-dimensional real (unit) vector *n*.

Parameters

theta	Rotation angle
n	3-dimensional real (unit) vector

Returns

Rotation gate

7.15.3.10 RX()

Qubit rotation of theta about the X axis.

Parameters

theta	Rotation angle
-------	----------------

Returns

Rotation gate

7.15.3.11 RY()

Qubit rotation of *theta* about the Y axis.

Parameters

Returns

Rotation gate

7.15.3.12 RZ()

Qubit rotation of theta about the Z axis.

Parameters

```
theta Rotation angle
```

Returns

Rotation gate

7.15.3.13 SWAPd()

```
cmat qpp::Gates::SWAPd (
        idx D = 2 ) const [inline]
```

SWAP gate for qudits.

Parameters

D Dimension of the Hilbert space

Returns

SWAP gate for qudits

7.15.3.14 Xd()

```
cmat qpp::Gates::Xd (
    idx D = 2 ) const [inline]
```

Generalized X gate for qudits.

Note

```
Defined as X=\sum_{j=0}^{D-1}|j\oplus 1\rangle\langle j|, i.e. raising operator X|j\rangle=|j\oplus 1\rangle
```

Parameters

D Dimension of the Hilbert space

Returns

Generalized X gate for qudits

7.15.3.15 Zd()

```
cmat qpp::Gates::Zd (
    idx D = 2 ) const [inline]
```

Generalized Z gate for qudits.

Note

Defined as
$$Z = \sum_{j=0}^{D-1} \exp(2\pi \mathrm{i} j/D) |j\rangle\langle j|$$

Parameters

D Dimension of the Hilbert space

Returns

Generalized Z gate for qudits

7.15.4 Friends And Related Function Documentation

```
7.15.4.1 internal::Singleton < const Gates >
friend class internal::Singleton < const Gates > [friend]
```

7.15.5 Member Data Documentation

```
7.15.5.1 CNOT
```

```
cmat qpp::Gates::CNOT {cmat::Identity(4, 4)}
```

Controlled-NOT control target gate.

7.15.5.2 CNOTba

```
cmat qpp::Gates::CNOTba {cmat::Zero(4, 4)}
```

Controlled-NOT target->control gate.

7.15.5.3 CZ

```
cmat qpp::Gates::CZ {cmat::Identity(4, 4)}
```

Controlled-Phase gate.

7.15.5.4 FRED

```
cmat qpp::Gates::FRED {cmat::Identity(8, 8)}
```

Fredkin gate.

```
7.15.5.5 H
cmat qpp::Gates::H {cmat::Zero(2, 2)}
Hadamard gate.
7.15.5.6 ld2
cmat qpp::Gates::Id2 {cmat::Identity(2, 2)}
Identity gate.
7.15.5.7 S
cmat qpp::Gates::S {cmat::Zero(2, 2)}
S gate.
7.15.5.8 SWAP
cmat qpp::Gates::SWAP {cmat::Identity(4, 4)}
SWAP gate.
7.15.5.9 T
cmat qpp::Gates::T {cmat::Zero(2, 2)}
T gate.
7.15.5.10 TOF
cmat qpp::Gates::TOF {cmat::Identity(8, 8)}
Toffoli gate.
```

7.15.5.11 X

```
cmat qpp::Gates::X {cmat::Zero(2, 2)}
```

Pauli Sigma-X gate.

7.15.5.12 Y

```
cmat qpp::Gates::Y {cmat::Zero(2, 2)}
```

Pauli Sigma-Y gate.

7.15.5.13 Z

```
cmat qpp::Gates::Z {cmat::Zero(2, 2)}
```

Pauli Sigma-Z gate.

The documentation for this class was generated from the following file:


· classes/gates.h

7.16 qpp::QCircuit::GateStep Struct Reference

One step consisting only of gates/operators in the circuit.

```
#include <classes/circuits.h>
```

Collaboration diagram for qpp::QCircuit::GateStep:



Public Member Functions

• GateStep ()=default

Default constructor.

GateStep (GateType gate_type, const cmat &gate, const std::vector< idx > &ctrl, const std::vector< idx > &target, std::string name="")

Constructs a gate step instance.

Public Attributes

```
    GateType gate_type_ = GateType::NONE
        gate type
    cmat gate_
        gate
    std::vector < idx > ctrl_
        control
    std::vector < idx > target_
        target where the gate is applied
    std::string name_
        custom name of the step
```

7.16.1 Detailed Description

7.16.2.1 GateStep() [1/2]

One step consisting only of gates/operators in the circuit.

7.16.2 Constructor & Destructor Documentation

Constructs a gate step instance.

Parameters

gate_type	Gate type
gate	Quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes
step_no	Circuit step number
name	Optional gate name

7.16.3 Member Data Documentation

```
7.16.3.1 ctrl_
std::vector<idx> qpp::QCircuit::GateStep::ctrl_
control
7.16.3.2 gate_
cmat qpp::QCircuit::GateStep::gate_
gate
7.16.3.3 gate_type_
GateType qpp::QCircuit::GateStep::gate_type_ = GateType::NONE
gate type
7.16.3.4 name_
std::string qpp::QCircuit::GateStep::name_
```

custom name of the step

7.16.3.5 target_

```
std::vector<idx> qpp::QCircuit::GateStep::target_
```

target where the gate is applied

The documentation for this struct was generated from the following file:


· classes/circuits.h

7.17 qpp::IDisplay Class Reference

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

```
#include <classes/idisplay.h>
```

Inheritance diagram for qpp::IDisplay:



Public Member Functions

- IDisplay ()=default
 - Default constructor.
- IDisplay (const IDisplay &)=default
 - Default copy constructor.
- IDisplay (IDisplay &&)=default

Default move constructor.

IDisplay & operator= (const IDisplay &)=default

Default copy assignment operator.

• IDisplay & operator= (IDisplay &&)=default

Default move assignment operator.

virtual ∼IDisplay ()=default

Default virtual destructor.

Private Member Functions

virtual std::ostream & display (std::ostream &os) const =0
 Must be overridden by all derived classes.

Friends

std::ostream & operator<< (std::ostream &os, const IDisplay &rhs)
 Overloads the extraction operator.

7.17.1 Detailed Description

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

This class defines friend inline std::ostream& operator<< (std::ostream& os, const qpp::IDisplay& rhs). The latter delegates the work to the pure private virtual function qpp::IDisplay::display() which has to be overridden by all derived classes.

7.17.2 Constructor & Destructor Documentation

```
7.17.2.1 | Display() [1/3]

qpp::IDisplay::IDisplay ( ) [default]

Default constructor.
```

Default copy constructor.

Default move constructor.

```
7.17.2.4 \simIDisplay()
```

```
virtual qpp::IDisplay::~IDisplay ( ) [virtual], [default]
```

Default virtual destructor.

7.17.3 Member Function Documentation

```
7.17.3.1 display()
```

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

 $\label{local-problem} \begin{array}{llll} \textbf{Implemented} & \textbf{in} & \textbf{qpp::QEngine,} & \textbf{qpp::QCircuit,} & \textbf{qpp::QCircuit::iterator::value_type_,} & \textbf{qpp::Dynamic_bitset,} \\ \textbf{qpp::internal::IOManipEigen,} & \textbf{qpp::Timer} < \textbf{T, CLOCK_T} >, & \textbf{qpp::internal::IOManipPointer} < \textbf{PointerType} >, & \textbf{and} \\ \textbf{qpp::internal::IOManipRange} < \textbf{InputIterator} >. \end{array}$

```
7.17.3.2 operator=() [1/2]
```

Default copy assignment operator.

```
7.17.3.3 operator=() [2/2]
```

Default move assignment operator.

7.17.4 Friends And Related Function Documentation

7.17.4.1 operator <<

```
std::ostream& operator<< (
          std::ostream & os,
          const IDisplay & rhs ) [friend]</pre>
```

Overloads the extraction operator.

Delegates the work to the virtual function qpp::IDisplay::display()

The documentation for this class was generated from the following file:


· classes/idisplay.h

7.18 qpp::IJSON Class Reference

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

```
#include <classes/idisplay.h>
```

Inheritance diagram for qpp::IJSON:



Public Member Functions

• IJSON ()=default

Default constructor.

• IJSON (const IJSON &)=default

Default copy constructor.

• IJSON (IJSON &&)=default

Default move constructor.

• IJSON & operator= (const IJSON &)=default

Default copy assignment operator.

• IJSON & operator= (IJSON &&)=default

Default move assignment operator.

virtual ∼IJSON ()=default

Default virtual destructor.

virtual std::string to_JSON (bool enclosed_in_curly_brackets=true) const =0

JSON representation of the derived instance, must be overridden by all derived classes.

7.18.1 Detailed Description

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

7.18.2 Constructor & Destructor Documentation

Default constructor.

Default copy constructor.

Default move constructor.

```
7.18.2.4 \simIJSON() virtual qpp::IJSON::\simIJSON ( ) [virtual], [default]
```

Default virtual destructor.

7.18.3 Member Function Documentation

Default copy assignment operator.

Default move assignment operator.

JSON representation of the derived instance, must be overridden by all derived classes.

Parameters

Implemented in qpp::QEngine, and qpp::QCircuit.

The documentation for this class was generated from the following file:


· classes/idisplay.h

7.19 qpp::Init Class Reference


const Singleton class that performs additional initializations/cleanups

```
#include <classes/init.h>
```

Inheritance diagram for qpp::Init:



Collaboration diagram for qpp::Init:



Private Member Functions

- Init ()
 - Additional initializations.
- ∼Init ()

Cleanups.

Friends

class internal::Singleton < const Init >

Additional Inherited Members

7.19.1 Detailed Description

const Singleton class that performs additional initializations/cleanups

7.19.2 Constructor & Destructor Documentation

```
7.19.2.1 Init()

qpp::Init::Init ( ) [inline], [private]

Additional initializations.
```

```
7.19.2.2 ~ Init()

qpp::Init::~Init ( ) [inline], [private]
```

Cleanups.

7.19.3 Friends And Related Function Documentation

```
7.19.3.1 internal::Singleton < const Init >
friend class internal::Singleton < const Init > [friend]
```

The documentation for this class was generated from the following file:


• classes/init.h

7.20 qpp::exception::InvalidIterator Class Reference


Invalid iterator.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::InvalidIterator:



Collaboration diagram for qpp::exception::InvalidIterator:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.20.1 Detailed Description

Invalid iterator.

7.20.2 Member Function Documentation

7.20.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.20.2.2 type_description()

std::string qpp::exception::InvalidIterator::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

• classes/exception.h


7.21 qpp::internal::IOManipEigen Class Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipEigen:



Collaboration diagram for qpp::internal::IOManipEigen:



Public Member Functions

- template<typename Derived > IOManipEigen (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
- IOManipEigen (const cplx z, double chop=qpp::chop)

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- cmat A_
- double chop_

7.21.1 Constructor & Destructor Documentation

7.21.2 Member Function Documentation

```
7.21.2.1 display()
```

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.21.3 Member Data Documentation

```
7.21.3.1 A_
```

```
cmat qpp::internal::IOManipEigen::A_ [private]
```

7.21.3.2 chop_

double qpp::internal::IOManipEigen::chop_ [private]


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


7.22 qpp::internal::IOManipPointer< PointerType > Class Template Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipPointer< PointerType >:



Collaboration diagram for qpp::internal::IOManipPointer< PointerType >:



Public Member Functions

- IOManipPointer (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")
- IOManipPointer (const IOManipPointer &)=default
- IOManipPointer & operator= (const IOManipPointer &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- const PointerType * p_
- idx N_
- std::string separator_
- std::string start
- std::string end_

7.22.1 Constructor & Destructor Documentation

7.22.1.1 IOManipPointer() [1/2]

7.22.1.2 IOManipPointer() [2/2]

7.22.2 Member Function Documentation

7.22.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.22.2.2 operator=()

7.22.3 Member Data Documentation

```
7.22.3.1 end_
```

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::end_ [private]
```

7.22.3.2 N_

```
template<typename PointerType>
idx qpp::internal::IOManipPointer< PointerType >::N_ [private]
```

7.22.3.3 p_

```
template<typename PointerType>
const PointerType* qpp::internal::IOManipPointer< PointerType >::p_ [private]
```

7.22.3.4 separator_

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::separator_ [private]
```

7.22.3.5 start

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::start_ [private]
```


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


7.23 qpp::internal::IOManipRange < InputIterator > Class Template Reference

```
#include <internal/classes/iomanip.h>
```

Inheritance diagram for qpp::internal::IOManipRange< InputIterator >:



Collaboration diagram for qpp::internal::IOManipRange< InputIterator >:



Public Member Functions

- IOManipRange (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")
- IOManipRange (const IOManipRange &)=default
- IOManipRange & operator= (const IOManipRange &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- InputIterator first_
- InputIterator last_
- std::string separator_
- std::string start_
- std::string end_

7.23.1 Constructor & Destructor Documentation

7.23.1.1 IOManipRange() [1/2]

7.23.1.2 IOManipRange() [2/2]

7.23.2 Member Function Documentation

7.23.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.23.2.2 operator=()

7.23.3 Member Data Documentation

```
7.23.3.1 end_
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::end_ [private]
7.23.3.2 first_
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::first_ [private]
7.23.3.3 last_
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::last_ [private]
7.23.3.4 separator_
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::separator_ [private]
```

```
7.23.3.5 start_
```

```
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::start_ [private]
```

The documentation for this class was generated from the following file:

• internal/classes/iomanip.h

7.24 qpp::is_complex< T > Struct Template Reference


Checks whether the type is a complex type.

#include <traits.h>

Inheritance diagram for qpp::is_complex< T >:



Collaboration diagram for qpp::is_complex< T >:



7.24.1 Detailed Description

template<typename T> struct qpp::is_complex< T>

Checks whether the type is a complex type.

Provides the constant member *value* which is equal to *true*, if the type is a complex type, i.e. *std::complex<T>*

The documentation for this struct was generated from the following file:

7.25 qpp::is_complex < std::complex < T > > Struct Template Reference


Checks whether the type is a complex number type, specialization for complex types.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_complex < std::complex < T > :



Collaboration diagram for qpp::is_complex< std::complex< T >>:



7.25.1 Detailed Description

```
template<typename T> struct qpp::is_complex< std::complex< T > >
```

Checks whether the type is a complex number type, specialization for complex types.


The documentation for this struct was generated from the following file:

7.26 qpp::is_iterable < T, typename > Struct Template Reference


Checks whether T is compatible with an STL-like iterable container.

#include <traits.h>

Inheritance diagram for qpp::is_iterable < T, typename >:



Collaboration diagram for qpp::is_iterable < T, typename >:



7.26.1 Detailed Description

template<typename T, typename = void> struct qpp::is_iterable< T, typename >

Checks whether T is compatible with an STL-like iterable container.

Provides the constant member *value* which is equal to *true*, if *T* is compatible with an iterable container, i.e. provides at least *begin()* and *end()* member functions and allows de-referencing. Otherwise, *value* is equal to *false*.


The documentation for this struct was generated from the following file:

7.27 qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().begin())) > Struct Template Reference

Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(*(std::declval < T >().begin())) > :



Collaboration diagram for qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std:: \leftarrow :declval< T >().end()), decltype(*(std::declval< T >().begin()))>>:



7.27.1 Detailed Description

 $template < typename \ T > \\ struct \ qpp::is_iterable < T, \ to_void < decltype(std::declval < T > ().begin()), \ decltype(std::declval < T > ().end()), \ decltype(*(std::declval < T > ().begin())) > \\ ::declval < T > ().begin())) > \\$

Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

The documentation for this struct was generated from the following file:

· traits.h

7.28 qpp::is_matrix_expression < Derived > Struct Template Reference


Checks whether the type is an Eigen matrix expression.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_matrix_expression< Derived >:



Collaboration diagram for qpp::is_matrix_expression< Derived >:



7.28.1 Detailed Description

template < typename Derived > struct qpp::is_matrix_expression < Derived >

Checks whether the type is an Eigen matrix expression.

Provides the constant member *value* which is equal to *true*, if the type is an Eigen matrix expression of type *Eigen* :: *MatrixBase* < *Derived* >. Otherwise, *value* is equal to *false*.


The documentation for this struct was generated from the following file:

7.29 qpp::QCircuit::iterator Class Reference

Quantum circuit bound-checking (safe) iterator.

#include <classes/circuits.h>

Collaboration diagram for qpp::QCircuit::iterator:



Classes

struct value_type_

Public Types

• using difference_type = long long

iterator trait

using value_type = value_type_

iterator trait

using pointer = const value_type *

iterator trait

using reference = const value_type &

iterator trait

• using iterator_category = std::forward_iterator_tag

iterator trait

Public Member Functions

• iterator ()=default

Default constructor.

• iterator (const iterator &)=default

Default copy constructor.

• iterator & operator= (const iterator &)=default

Default copy assignment operator.

• iterator & operator++ ()

Prefix increment operator.

iterator operator++ (int)

Postfix increment operator.

• bool operator== (const iterator &rhs) const

Equality operator.

bool operator!= (iterator rhs) const

Inequality operator.

• const value_type_ & operator* () const

Safe de-referencing operator.

void set_begin_ (const QCircuit *qcd)

Sets the iterator to std::begin(this)

void set_end_ (const QCircuit *qcd)

Sets the iterator to std::begin(this)

Private Attributes

```
const QCircuit * qcd_ {nullptr}
```

< non-owning pointer to const quantum circuit

value_type_ elem_ {nullptr}

7.29.1 Detailed Description

Quantum circuit bound-checking (safe) iterator.

Note

The iterator is a const_iterator by default

7.29.2 Member Typedef Documentation

```
7.29.2.1 difference_type
```

```
using qpp::QCircuit::iterator::difference_type = long long
```

iterator trait

7.29.2.2 iterator_category

```
using qpp::QCircuit::iterator::iterator_category = std::forward_iterator_tag
```

iterator trait

7.29.2.3 pointer

```
using qpp::QCircuit::iterator::pointer = const value_type*
```

iterator trait

7.29.2.4 reference

```
using qpp::QCircuit::iterator::reference = const value_type&
```

iterator trait

7.29.2.5 value_type

```
using qpp::QCircuit::iterator::value_type = value_type_
```

iterator trait

7.29.3 Constructor & Destructor Documentation

```
7.29.3.1 iterator() [1/2]
```

```
qpp::QCircuit::iterator::iterator ( ) [default]
```

Default constructor.

```
7.29.3.2 iterator() [2/2]
```

Default copy constructor.

7.29.4 Member Function Documentation

7.29.4.1 operator"!=()

Inequality operator.

Parameters

rhs | Iterator against which the inequality is being tested

Returns

True if the iterators are not equal (bit by bit), false otherwise

7.29.4.2 operator*()

```
const value_type_& qpp::QCircuit::iterator::operator* ( ) const [inline]
```

Safe de-referencing operator.

Returns

Constant reference to the iterator element

7.29.4.3 operator++() [1/2]

```
iterator& qpp::QCircuit::iterator::operator++ ( ) [inline]
```

Prefix increment operator.

Returns

Reference to the current instance

7.29.4.4 operator++() [2/2]

Postfix increment operator.

Returns

Copy of the current instance before the increment

```
7.29.4.5 operator=()
```

Default copy assignment operator.

Returns

Reference to the current instance

```
7.29.4.6 operator==()
```

Equality operator.

Parameters

rhs | Iterator against which the equality is being tested

Returns

True if the iterators are equal, false otherwise

```
7.29.4.7 set_begin_()
```

Sets the iterator to std::begin(this)

Parameters

qcd | Constant pointer to a quantum circuit

```
7.29.4.8 set_end_()
```

Sets the iterator to std::begin(this)

Parameters

qcd Constant pointer to a quantum circuit

7.29.5 Member Data Documentation

```
7.29.5.1 elem_
value_type_ qpp::QCircuit::iterator::elem_ {nullptr} [private]

7.29.5.2 qcd_
const QCircuit* qpp::QCircuit::iterator::qcd_ {nullptr} [private]
```

The documentation for this class was generated from the following file:

· classes/circuits.h

7.30 qpp::make_void < Ts > Struct Template Reference

Helper for qpp::to_void<>> alias template.

< non-owning pointer to const quantum circuit

```
#include <traits.h>
```

Public Types

• typedef void type

7.30.1 Detailed Description

```
template<typename... Ts>
struct qpp::make_void< Ts>
```

Helper for qpp::to_void<>> alias template.

See also

qpp::to_void<>

7.30.2 Member Typedef Documentation

7.30.2.1 type

```
template<typename... Ts>
typedef void qpp::make_void< Ts >::type
```

The documentation for this struct was generated from the following file:


• traits.h

7.31 qpp::exception::MatrixMismatchSubsys Class Reference


Matrix mismatch subsystems exception.

```
#include <classes/exception.h>
```

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Mismatch Subsys:$



Collaboration diagram for qpp::exception::MatrixMismatchSubsys:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.31.1 Detailed Description

Matrix mismatch subsystems exception.

Matrix size mismatch subsystem sizes (e.g. in qpp::apply())

7.31.2 Member Function Documentation

7.31.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred
-------	--

7.31.2.2 type_description()

std::string qpp::exception::MatrixMismatchSubsys::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.32 qpp::exception::MatrixNotCvector Class Reference


Matrix is not a column vector exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Cvector:$



Collaboration diagram for qpp::exception::MatrixNotCvector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.32.1 Detailed Description

Matrix is not a column vector exception.

Eigen::Matrix is not a column vector

7.32.2 Member Function Documentation

7.32.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred
-------	--

7.32.2.2 type_description()

std::string qpp::exception::MatrixNotCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.33 qpp::exception::MatrixNotRvector Class Reference


Matrix is not a row vector exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Rvector:$



Collaboration diagram for qpp::exception::MatrixNotRvector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.33.1 Detailed Description

Matrix is not a row vector exception.

Eigen::Matrix is not a row vector

7.33.2 Member Function Documentation

7.33.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred
-------	--

7.33.2.2 type_description()

std::string qpp::exception::MatrixNotRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.34 qpp::exception::MatrixNotSquare Class Reference


Matrix is not square exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception::MatrixNotSquare:$



 $Collaboration\ diagram\ for\ qpp::exception::MatrixNotSquare:$



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.34.1 Detailed Description

Matrix is not square exception.

Eigen::Matrix is not a square matrix

7.34.2 Member Function Documentation

7.34.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where Text representing where the exception occurred
--

7.34.2.2 type_description()

std::string qpp::exception::MatrixNotSquare::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.35 qpp::exception::MatrixNotSquareNorCvector Class Reference


Matrix is not square nor column vector exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Square Nor Cvector:$



Collaboration diagram for qpp::exception::MatrixNotSquareNorCvector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.35.1 Detailed Description

Matrix is not square nor column vector exception.

Eigen::Matrix is not a square matrix nor a column vector

7.35.2 Member Function Documentation

7.35.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where Text representing where the exception occ

7.35.2.2 type_description()

std::string qpp::exception::MatrixNotSquareNorCvector::type_description () const [inline],
[override], [virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.36 qpp::exception::MatrixNotSquareNorRvector Class Reference


Matrix is not square nor row vector exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Square Nor Rvector:$



Collaboration diagram for qpp::exception::MatrixNotSquareNorRvector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.36.1 Detailed Description

Matrix is not square nor row vector exception.

Eigen::Matrix is not a square matrix nor a row vector

7.36.2 Member Function Documentation

7.36.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.36.2.2 type_description()

```
std::string qpp::exception::MatrixNotSquareNorRvector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.37 qpp::exception::MatrixNotSquareNorVector Class Reference


Matrix is not square nor vector exception.

```
#include <classes/exception.h>
```

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Square Nor Vector:$



Collaboration diagram for qpp::exception::MatrixNotSquareNorVector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.37.1 Detailed Description

Matrix is not square nor vector exception.

Eigen::Matrix is not a square matrix nor a row/column vector

7.37.2 Member Function Documentation

7.37.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred
-------	--

7.37.2.2 type_description()

std::string qpp::exception::MatrixNotSquareNorVector::type_description () const [inline],
[override], [virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.38 qpp::exception::MatrixNotVector Class Reference


Matrix is not a vector exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception::MatrixNotVector:$



Collaboration diagram for qpp::exception::MatrixNotVector:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.38.1 Detailed Description

Matrix is not a vector exception.

Eigen::Matrix is not a row or column vector

7.38.2 Member Function Documentation

7.38.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.38.2.2 type_description()

std::string qpp::exception::MatrixNotVector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.39 qpp::QCircuit::MeasureStep Struct Reference

One step consisting only of measurements in the circuit.

```
#include <classes/circuits.h>
```

Collaboration diagram for qpp::QCircuit::MeasureStep:



Public Member Functions

• MeasureStep ()=default

Default constructor.

MeasureStep (MeasureType measurement_type, const std::vector < cmat > &mats, const std::vector < idx > &target, idx c_reg, std::string name="")

Constructs a measurement step instance.

Public Attributes

MeasureType measurement_type_ = MeasureType::NONE

measurement type

- std::vector< cmat > mats
- std::vector < idx > target_

target where the measurement is applied

- idx c_reg_ {}
- · std::string name_

custom name of the step

7.39.1 Detailed Description

One step consisting only of measurements in the circuit.

7.39.2 Constructor & Destructor Documentation

```
7.39.2.1 MeasureStep() [1/2]

qpp::QCircuit::MeasureStep::MeasureStep ( ) [default]
```

Default constructor.

7.39.2.2 MeasureStep() [2/2]

Constructs a measurement step instance.

Parameters

measurement_type	Measurement type
mats	Vector of measurement matrices (can be only one or many for Kraus measurements)
target	Target qudit indexes
c_reg	Classical register where the value of the measurement is stored
step_no	Circuit step number
name	Optional gate name

7.39.3 Member Data Documentation

```
7.39.3.1 c_reg_
```

```
idx qpp::QCircuit::MeasureStep::c_reg_ {}
```

index of the classical register where the measurement result is being stored

```
7.39.3.2 mats_
```

```
std::vector<cmat> qpp::QCircuit::MeasureStep::mats_
```

matrix/matrices that specify the measurement

7.39.3.3 measurement_type_

```
MeasureType qpp::QCircuit::MeasureStep::measurement_type_ = MeasureType::NONE
```

measurement type

```
7.39.3.4 name_
```

```
std::string qpp::QCircuit::MeasureStep::name_
```

custom name of the step

7.39.3.5 target_

```
std::vector<idx> qpp::QCircuit::MeasureStep::target_
```

target where the measurement is applied

The documentation for this struct was generated from the following file:


· classes/circuits.h

7.40 qpp::exception::NoCodeword Class Reference


Codeword does not exist exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::NoCodeword:



Collaboration diagram for qpp::exception::NoCodeword:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.40.1 Detailed Description

Codeword does not exist exception.

Codeword does not exist, thrown when calling qpp::Codes::codeword() with an invalid index

7.40.2 Member Function Documentation

7.40.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.40.2.2 type_description()

```
std::string qpp::exception::NoCodeword::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.41 qpp::NoiseBase < T > Class Template Reference

Base class for all noise models, derive your particular noise model.

```
#include <classes/noise.h>
```

Collaboration diagram for qpp::NoiseBase< T >:



Public Types

using noise_type = T

Public Member Functions

• template<typename U = noise_type>

NoiseBase (const std::vector< cmat > &Ks, typename std::enable_if< std::is_same< NoiseType::StateDependent, U >::value >::type *=nullptr)

Constructs a noise instance for StateDependent noise type.

• template<typename U = noise_type>

NoiseBase (const std::vector< cmat > &Ks, const std::vector< double > &probs, typename std::enable_if< std::is same< NoiseType::StateIndependent, U >::value >::type *=nullptr)

Constructs a noise instance for StateIndependent noise type.

virtual ∼NoiseBase ()=default

Default virtual destructor.

idx get_d () const noexcept

Qudit dimension.

std::vector< cmat > get_Ks () const

Vector of noise operators.

std::vector< double > get_probs () const

Vector of probabilities corresponding to each noise operator.

• idx get last idx () const

Index of the last occurring noise element.

double get_last_p () const

Probability of the last occurring noise element.

cmat get_last_K () const

Last occurring noise element.

· virtual cmat operator() (const cmat &state, idx target) const

Function invocation operator, applies the underlying noise model on qudit target of the multi-partite state vector or density matrix state.

virtual cmat operator() (const cmat &state, const std::vector < idx > &target) const

Function invocation operator, applies the underlying correlated noise model on qudits specified by target of the multipartite state vector or density matrix state.

Protected Member Functions

void compute_probs_ (const cmat &state, const std::vector < idx > &target) const
 Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

• cmat compute state (const cmat &state, const std::vector < idx > &target) const

Compute the resulting state after the noise was applied.

Protected Attributes

const std::vector< cmat > Ks

Kraus operators.

std::vector< double > probs_

probabilities

• idx d_ {}

qudit dimension

idx i_{}

index of the last occurring noise element

bool generated_ {false}

invoked, or if the noise is state-independent

7.41.1 Detailed Description

```
\label{eq:template} \begin{split} \text{template} &< \text{class T}> \\ \text{class qpp::NoiseBase} &< \text{T}> \end{split}
```

Base class for all noise models, derive your particular noise model.

7.41.2 Member Typedef Documentation

7.41.2.1 noise_type

```
template<class T>
using qpp::NoiseBase< T >::noise_type = T
```

7.41.3 Constructor & Destructor Documentation

7.41.3.1 NoiseBase() [1/2]

Constructs a noise instance for StateDependent noise type.

Note

SFINAEd-out for StateIndependent noise

Parameters

Α	Eigen expression (state vector or density matrix)
Ks	Vector of noise (Kraus) operators that specify the noise
d	Subsystem dimension

7.41.3.2 NoiseBase() [2/2]

template<class T>

Constructs a noise instance for StateIndependent noise type.

Note

SFINAEd-out for StateDependent noise

Parameters

Α	Eigen expression (state vector or density matrix)
Ks	Vector of noise (Kraus) operators that specify the noise
d	Subsystem dimension

7.41.3.3 ∼NoiseBase()

```
template<class T>
virtual qpp::NoiseBase< T >::~NoiseBase ( ) [virtual], [default]
```

Default virtual destructor.

7.41.4 Member Function Documentation

7.41.4.1 compute_probs_()

Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

Parameters

state	State vector or density matrix
target	Qudit indexes where the noise is applied

7.41.4.2 compute_state_()

Compute the resulting state after the noise was applied.

Parameters

state	State vector or density matrix
target	Qudit indexes where the noise is applied

Returns

Resulting state after the noise was applied

7.41.4.3 get_d()

```
template<class T>
idx qpp::NoiseBase< T >::get_d ( ) const [inline], [noexcept]
```

Qudit dimension.

Returns

Qudit dimension

7.41.4.4 get_Ks()

```
template<class T>
std::vector<cmat> qpp::NoiseBase< T >::get_Ks () const [inline]
```

Vector of noise operators.

Returns

Vector of noise operators

```
7.41.4.5 get_last_idx()
```

```
template<class T>
idx qpp::NoiseBase< T >::get_last_idx ( ) const [inline]
```

Index of the last occurring noise element.

Returns

Index of the last occurring noise element

```
7.41.4.6 get_last_K()
```

```
template<class T>
cmat qpp::NoiseBase< T >::get_last_K ( ) const [inline]
```

Last occurring noise element.

Returns

Last occurring noise element

```
7.41.4.7 get_last_p()
```

```
template<class T>
double qpp::NoiseBase< T >::get_last_p ( ) const [inline]
```

Probability of the last occurring noise element.

Returns

Probability of the last occurring noise element

```
7.41.4.8 get_probs()
```

```
template<class T>
std::vector<double> qpp::NoiseBase< T >::get_probs ( ) const [inline]
```

Vector of probabilities corresponding to each noise operator.

Returns

Probability vector

```
7.41.4.9 operator()() [1/2]
```

Function invocation operator, applies the underlying noise model on qudit *target* of the multi-partite state vector or density matrix *state*.

Parameters

state	Multi-partite state vector or density matrix
target	Qudit index where the noise is applied

Returns

Resulting state vector or density matrix

7.41.4.10 operator()() [2/2]

Function invocation operator, applies the underlying correlated noise model on qudits specified by *target* of the multi-partite state vector or density matrix *state*.

Parameters

state	Multi-partite state vector or density matrix
target	Qudit indexes where the correlated noise is applied

Returns

Resulting state vector or density matrix

7.41.5 Member Data Documentation

7.41.5.1 d_

```
template<class T>
idx qpp::NoiseBase< T >::d_ {} [mutable], [protected]
qudit dimension
```

7.41.5.2 generated_

```
template<class T>
bool qpp::NoiseBase< T >::generated_ {false} [mutable], [protected]
```

invoked, or if the noise is state-independent

set to true after compute_state_() is

7.41.5.3 i_

```
template<class T>
idx qpp::NoiseBase< T >::i_ {} [mutable], [protected]
```

index of the last occurring noise element

7.41.5.4 Ks_

```
template<class T>
const std::vector<cmat> qpp::NoiseBase< T >::Ks_ [protected]
```

Kraus operators.

7.41.5.5 probs

```
template<class T>
std::vector<double> qpp::NoiseBase< T >::probs_ [mutable], [protected]
```

probabilities

The documentation for this class was generated from the following file:

• classes/noise.h

7.42 qpp::NoiseType Class Reference

Contains template tags used to specify the noise type.

```
#include <classes/noise.h>
```

Classes

class StateDependent

Template tag, used whenever the noise is state-dependent.

· class StateIndependent

Template tag, used whenever the noise is state-independent.

7.42.1 Detailed Description

Contains template tags used to specify the noise type.

The documentation for this class was generated from the following file:


· classes/noise.h

7.43 qpp::exception::NotBipartite Class Reference


Not bi-partite exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotBipartite:



Collaboration diagram for qpp::exception::NotBipartite:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.43.1 Detailed Description

Not bi-partite exception.

std::vector<idx> of dimensions has size different from 2

7.43.2 Member Function Documentation

7.43.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.43.2.2 type_description()

```
std::string qpp::exception::NotBipartite::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.44 qpp::exception::NotImplemented Class Reference


Code not yet implemented.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotImplemented:



Collaboration diagram for qpp::exception::NotImplemented:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.44.1 Detailed Description

Code not yet implemented.

7.44.2 Member Function Documentation

7.44.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.44.2.2 type_description()

```
std::string qpp::exception::NotImplemented::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.45 qpp::exception::NotQubitCvector Class Reference


Column vector is not 2 x 1 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitCvector:



Collaboration diagram for qpp::exception::NotQubitCvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.45.1 Detailed Description

Column vector is not 2 x 1 exception.

Eigen::Matrix is not 2 x 1

7.45.2 Member Function Documentation

7.45.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.45.2.2 type_description()

std::string qpp::exception::NotQubitCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.46 qpp::exception::NotQubitMatrix Class Reference


Matrix is not 2 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitMatrix:



Collaboration diagram for qpp::exception::NotQubitMatrix:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.46.1 Detailed Description

Matrix is not 2 x 2 exception.

Eigen::Matrix is not 2 x 2

7.46.2 Member Function Documentation

7.46.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.46.2.2 type_description()

std::string qpp::exception::NotQubitMatrix::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.47 qpp::exception::NotQubitRvector Class Reference


Row vector is not 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitRvector:



Collaboration diagram for qpp::exception::NotQubitRvector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.47.1 Detailed Description

Row vector is not 1 x 2 exception.

Eigen::Matrix is not 1 x 2

7.47.2 Member Function Documentation

7.47.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.47.2.2 type_description()

std::string qpp::exception::NotQubitRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.48 qpp::exception::NotQubitSubsys Class Reference


Subsystems are not qubits exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitSubsys:



Collaboration diagram for qpp::exception::NotQubitSubsys:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.48.1 Detailed Description

Subsystems are not qubits exception.

Subsystems are not 2-dimensional (qubits)

7.48.2 Member Function Documentation

7.48.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.48.2.2 type_description()

```
std::string qpp::exception::NotQubitSubsys::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.49 qpp::exception::NotQubitVector Class Reference


Vector is not 2 x 1 nor 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitVector:



Collaboration diagram for qpp::exception::NotQubitVector:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.49.1 Detailed Description

Vector is not 2 x 1 nor 1 x 2 exception.

Eigen::Matrix is not 2 x 1 nor 1 x 2

7.49.2 Member Function Documentation

7.49.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.49.2.2 type_description()

std::string qpp::exception::NotQubitVector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.50 qpp::exception::OutOfRange Class Reference


Argument out of range exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::OutOfRange:



Collaboration diagram for qpp::exception::OutOfRange:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.50.1 Detailed Description

Argument out of range exception.

Argument out of range

7.50.2 Member Function Documentation

7.50.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.50.2.2 type_description()

```
std::string qpp::exception::OutOfRange::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.51 qpp::exception::PermInvalid Class Reference


Invalid permutation exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermInvalid:



Collaboration diagram for qpp::exception::PermInvalid:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.51.1 Detailed Description

Invalid permutation exception.

std::vector<idx> does note represent a valid permutation

7.51.2 Member Function Documentation

7.51.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.51.2.2 type_description()

```
std::string qpp::exception::PermInvalid::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.52 qpp::exception::PermMismatchDims Class Reference


Permutation mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermMismatchDims:



Collaboration diagram for qpp::exception::PermMismatchDims:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.52.1 Detailed Description

Permutation mismatch dimensions exception.

Size of the std::vector<idx> representing the permutation is different from the size of the std::vector<idx> of dimensions

7.52.2 Member Function Documentation

7.52.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

7.52.2.2 type_description()

```
std::string qpp::exception::PermMismatchDims::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.53 qpp::QCircuit Class Reference


Quantum circuit class.

#include <classes/circuits.h>

Inheritance diagram for qpp::QCircuit:



Collaboration diagram for qpp::QCircuit:



Classes

• struct GateStep

One step consisting only of gates/operators in the circuit.

· class iterator

Quantum circuit bound-checking (safe) iterator.

struct MeasureStep

One step consisting only of measurements in the circuit.

Public Types

enum GateType {
 GateType::NONE, GateType::SINGLE, GateType::TWO, GateType::THREE,
 GateType::CUSTOM, GateType::FAN, GateType::QFT, GateType::TFQ,
 GateType::SINGLE_CTRL_SINGLE_TARGET, GateType::SINGLE_CTRL_MULTIPLE_TARGET, GateType::MULTIPLE_CTRL_MULTIPLE_CTRL_GateType::CUSTOM_CTRL, GateType::SINGLE_CTRL_SINGLE_TARGET, GateType::SINGLE_CCTRL_MULTIPLE_TARGET

GateType::MULTIPLE_cCTRL_MULTIPLE_TARGET, GateType::CUSTOM_cCTRL }

Type of gate being executed in a gate step.

• enum MeasureType { MeasureType::NONE, MeasureType::MEASURE_Z, MeasureType::MEASURE_V, MeasureType::MEASURE_V_MANY }

Type of measurement being executed in a measurement step.

enum StepType { StepType::NONE, StepType::GATE, StepType::MEASUREMENT }

Types of each step in the quantum circuit.

GateType::MULTIPLE cCTRL SINGLE TARGET,

· using const iterator = iterator

both iterators are const_iterators

Public Member Functions

• iterator begin ()

Iterator to the first element.

· const iterator begin () const noexcept

Constant iterator to the first element.

· const iterator cbegin () const noexcept

Constant iterator to the first element.

• iterator end ()

Iterator to the next to the last element.

const_iterator end () const noexcept

Constant iterator to the next to the last element.

· const iterator cend () const noexcept

Constant iterator to the next to the last element.

QCircuit (idx nq, idx nc=0, idx d=2, std::string name="")

Constructs a quantum circuit.

virtual ~QCircuit ()=default

Default virtual destructor.

• idx get_nq () const noexcept

Total number of qudits in the circuit.

• idx get_nc () const noexcept

Total number of classical dits in the circuit.

• idx get_d () const noexcept

Dimension of the comprising qudits.

const std::vector< MeasureStep > & get_measurements () const noexcept

Vector of qpp::QCircuit::MeasureStep.

const std::vector< GateStep > & get_gates () const noexcept

Vector of qpp::QCircuit::GateStep.

• std::string get_name () const

Quantum circuit name.

· idx get measured (idx i) const

Check whether qudit i was already measured.

std::vector < idx > get_measured () const

Vector of already measured gudit indexes.

std::vector< idx > get_non_measured () const

Vector of non-measured qudit indexes.

• idx get_gate_count () const noexcept

Quantum circuit total gate count.

idx get measurement count () const noexcept

Quantum circuit total measurement count.

• idx get_step_count () const noexcept

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

QCircuit & gate (const cmat &U, idx i, std::string name="")

Applies the single qudit gate U on single qudit i.

QCircuit & gate (const cmat &U, idx i, idx j, std::string name="")

Applies the two qudit gate U on qudits i and j.

• QCircuit & gate (const cmat &U, idx i, idx j, idx k, std::string name="")

Applies the three qudit gate U on qudits i, j and k.

QCircuit & gate fan (const cmat &U, const std::vector < idx > &target, std::string name="")

Applies the single qudit gate U on every qudit listed in target.

• QCircuit & gate_fan (const cmat &U, const std::initializer_list< idx > &target, std::string name="")

Applies the single qudit gate U on every qudit listed in target.

QCircuit & gate fan (const cmat &U, std::string name="")

Applies the single qudit gate U on every remaining non-measured qudit.

QCircuit & gate_custom (const cmat &U, const std::vector< idx > &target, std::string name="")

Jointly applies the custom multiple qudit gate U on the qudit indexes specified by target.

QCircuit & QFT (const std::vector < idx > &target, bool swap QPP_UNUSED_=true)

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & TFQ (const std::vector < idx > &target, bool swap QPP UNUSED =true)

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & CTRL (const cmat &U, idx ctrl, idx target, std::string name="")

Applies the single qudit controlled gate U with control qudit ctrl and target qudit target.

QCircuit & CTRL (const cmat &U, idx ctrl, const std::vector< idx > &target, std::string name="")

Applies the single qudit controlled gate U with control qudit ctrl on every qudit listed in target.

QCircuit & CTRL (const cmat &U, const std::vector< idx > &ctrl, idx target, std::string name="")

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on the target qudit target.

QCircuit & CTRL (const cmat &U, const std::vector< idx > &ctrl, const std::vector< idx > &target, std::string name="")

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on every qudit listed in target.

QCircuit & CTRL_custom (const cmat &U, const std::vector < idx > &ctrl, const std::vector < idx > &target, std::string name="")

Jointly applies the custom multiple-qudit controlled gate U with multiple control qudits listed in ctrl on the qudit indexes specified by target.

QCircuit & cCTRL (const cmat &U, idx ctrl_dit, idx target, std::string name=""")

Applies the single qubit controlled gate U with classical control dit ctrl and target qudit target.

QCircuit & cCTRL (const cmat &U, idx ctrl_dit, const std::vector < idx > &target, std::string name="")

Applies the single qudit controlled gate U with classical control dit ctrl on every qudit listed in target.

QCircuit & cCTRL (const cmat &U, const std::vector < idx > &ctrl_dits, idx target, std::string name="")

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on the target qudit target.

QCircuit & cCTRL (const cmat &U, const std::vector< idx > &ctrl_dits, const std::vector< idx > &target, std::string name="")

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on every qudit listed in target.

QCircuit & cCTRL_custom (const cmat &U, const std::vector< idx > &ctrl_dits, const std::vector< idx > &target, std::string name="")

Jointly applies the custom multiple-qudit controlled gate U with multiple classical control dits listed in ctrl on the qudit indexes specified by target.

• QCircuit & measureZ (idx target, idx c_reg, std::string name="")

Measurement of single qudit in the computational basis (Z-basis)

QCircuit & measureV (const cmat &V, idx target, idx c_reg, std::string name="")

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

QCircuit & measureV (const cmat &V, const std::vector< idx > &target, idx c_reg, std::string name="")

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix ν

std::ostream & display (std::ostream &os) const override

qpp::IDisplay::display() override

• std::string to_JSON (bool enclosed_in_curly_brackets=true) const override

qpp::IJOSN::to_JSON() override

Private Attributes

```
    const idx nq
```

number of qudits

· const idx nc_

number of classical "dits"

· const idx d_

qudit dimension

• std::string name_

optional circuit name

std::vector< bool > measured_

keeps track of the measured qudits

std::vector< GateStep > gates_{}{}

gates

std::vector< MeasureStep > measurements_{}{}

measurements

std::vector< StepType > step_types_{}

type of each step

Friends

std::ostream & operator<< (std::ostream &os, const GateType &gate_type)

Extraction operator overload for qpp::QCircuit::GateType enum class.

• std::ostream & operator<< (std::ostream &os, const GateStep &gate_step)

Extraction operator overload for qpp::QCircuit::GateStep class.

std::ostream & operator<< (std::ostream &os, const MeasureType &measure_type)

Extraction operator overload for qpp::QCircuit::MeasureType enum class.

std::ostream & operator<< (std::ostream &os, const MeasureStep &measure_step)

Extraction operator overload for qpp::QCircuit::MeasureStep class.

7.53.1 Detailed Description

Quantum circuit class.

See also

qpp::QEngine

7.53.2 Member Typedef Documentation

7.53.2.1 const_iterator

using qpp::QCircuit::const_iterator = iterator

both iterators are const_iterators

7.53.3 Member Enumeration Documentation

7.53.3.1 GateType

enum qpp::QCircuit::GateType [strong]

Type of gate being executed in a gate step.

Enumerator

Enumerator	
NONE	represents no gate
SINGLE	unitary gate on a single qudit
TWO	unitary gate on 2 qudits
THREE	unitary gate on 3 qudits
CUSTOM	custom gate on multiple qudits
FAN	same unitary gate on multiple qudits
QFT	quantum Fourier transform,
TFQ	quantum inverse Fourier transform,
SINGLE_CTRL_SINGLE_TARGET	one control and one target controlled 1 qudit unitary gate with
SINGLE_CTRL_MULTIPLE_TARGET	one control and multiple targets controlled 1 qudit unitary gate with
MULTIPLE_CTRL_SINGLE_TARGET	multiple controls and single target controlled 1 qudit unitary gate with
MULTIPLE_CTRL_MULTIPLE_TARGET	multiple controls and multiple targets controlled 1 qudit unitary gate with
CUSTOM_CTRL	and multiple targets custom controlled gate with multiple controls
SINGLE_cCTRL_SINGLE_TARGET	one classical control and one target controlled 1 qudit unitary gate with
Generated by boxygen TRL_MULTIPLE_TARGET	one classical control and multiple targets controlled 1 qudit unitary gate with
MULTIPLE_cCTRL_SINGLE_TARGET	multiple classical controls and single target controlled 1 qudit unitary gate with

7.53.3.2 MeasureType

```
enum qpp::QCircuit::MeasureType [strong]
```

Type of measurement being executed in a measurement step.

Enumerator

NONE	represents no measurement
MEASURE_Z	Z measurement of single qudit.
MEASURE_V	or rank-1 projectors specified by the columns of matrix V measurement of single qudit in the orthonormal basis
MEASURE_V_MANY	basis or rank-1 projectors specified by the columns of matrix \it{V} measurement of multiple qudits in the orthonormal

7.53.3.3 StepType

```
enum qpp::QCircuit::StepType [strong]
```

Types of each step in the quantum circuit.

Enumerator

NONE	represents no step
GATE	quantum gate
MEASUREMENT	measurement

7.53.4 Constructor & Destructor Documentation

7.53.4.1 QCircuit()

```
qpp::QCircuit::QCircuit (
    idx nq,
    idx nc = 0,
    idx d = 2,
    std::string name = "" ) [inline], [explicit]
```

Constructs a quantum circuit.

Note

The measurement results can only be stored in the classical dits of which number is specified by nc

Parameters

nq	Number of qbits	
nc	Number of classical dits	
d	Subsystem dimensions (optional, default is qubit, i.e. $d = 2$)	
name	Circuit name (optional)	

7.53.4.2 ~QCircuit()

```
virtual qpp::QCircuit::~QCircuit ( ) [virtual], [default]
```

Default virtual destructor.

7.53.5 Member Function Documentation

```
7.53.5.1 begin() [1/2]
```

```
iterator qpp::QCircuit::begin ( ) [inline]
```

Iterator to the first element.

Returns

Iterator to the first element

```
7.53.5.2 begin() [2/2]
```

```
const_iterator qpp::QCircuit::begin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

7.53.5.3 cbegin()

```
const_iterator qpp::QCircuit::cbegin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

Applies the single qubit controlled gate *U* with classical control dit *ctrl* and target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with classical control dit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the
	classical control dits
name	Optional gate name Generated by Doxygen

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.53.5.7 cCTRL() [4/4]
```

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the classical control dits
name	Optional gate name

Returns

Reference to the current instance

7.53.5.8 cCTRL_custom()

Jointly applies the custom multiple-qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the qudit indexes specified by *target*.

Parameters

U	Multiple-qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit indexes where the gate U is applied depending on the values of the classical control dits
name	Optional gate name

Returns

Reference to the current instance

7.53.5.9 cend()

```
const_iterator qpp::QCircuit::cend ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

Returns

Constant iterator to the next to the last element

Applies the single qudit controlled gate *U* with control qudit *ctrl* and target qudit *target*.

std::string name = "") [inline]

Parameters

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with control qudit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

```
7.53.5.12 CTRL() [3/4]
```

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes; the gate <i>U</i> is applied on every one of them depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

7.53.5.14 CTRL_custom()

Jointly applies the custom multiple-qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the qudit indexes specified by *target*.

Parameters

U	Multiple-qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes where the gate U is applied depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

7.53.5.15 display()

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the quantum circuit

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.53.5.16 end() [1/2]
```

```
iterator qpp::QCircuit::end ( ) [inline]
```

Iterator to the next to the last element.

Returns

Iterator to the next to the last element

```
7.53.5.17 end() [2/2]
```

```
const_iterator qpp::QCircuit::end ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

Returns

Constant iterator to the next to the last element

Applies the single qudit gate *U* on single qudit *i*.

Parameters

U	Single qudit quantum gate
i	Qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the two qudit gate U on qudits i and j.

Parameters

U	Two qudit quantum gate
i	Qudit index
j	Qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the three qudit gate U on qudits i, j and k.

Parameters

U	Three qudit quantum gate
i	Qudit index
j	Qudit index
k	Qudit index
name	Optional gate name

Returns

Reference to the current instance

7.53.5.21 gate_custom()

Jointly applies the custom multiple qudit gate *U* on the qudit indexes specified by *target*.

Parameters

U	Multiple qudit quantum gate
target	Subsystem indexes where the gate U is applied
name	Optional gate name

Returns

Reference to the current instance

```
7.53.5.22 gate_fan() [1/3]
```

Applies the single qudit gate *U* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
target	Target qudit indexes; the gate U is applied on every one of them
name	Optional gate name

Returns

Reference to the current instance

std::string name = "") [inline]

Applies the single qudit gate *U* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
target	Target qudit indexes; the gate <i>U</i> is applied on every one of them
name	Optional gate name

const std::initializer_list< idx > & target,

Returns

Reference to the current instance

Applies the single qudit gate U on every remaining non-measured qudit.

Parameters

U	Single qudit quantum gate	
name	Optional gate name	

Returns

Reference to the current instance

```
7.53.5.25 get_d()
idx qpp::QCircuit::get_d ( ) const [inline], [noexcept]
```

Returns

Qudit dimension

Dimension of the comprising qudits.

```
7.53.5.26 get_gate_count()
idx qpp::QCircuit::get_gate_count ( ) const [inline], [noexcept]
```

Quantum circuit total gate count.

Returns

Total gate count

```
7.53.5.27 get_gates()
const std::vector<GateStep>& qpp::QCircuit::get_gates ( ) const [inline], [noexcept]
Vector of qpp::QCircuit::GateStep.
```

Returns

Vector of qpp::QCircuit::GateStep

```
7.53.5.28 get_measured() [1/2] idx qpp::QCircuit::get_measured ( idx i) const [inline]
```

Check whether qudit *i* was already measured.

D					
Pа	ra	m	ല	aı	r۹

i Qudit index

Returns

True if qudit i was already measured, false othwewise

```
7.53.5.29 get_measured() [2/2]
std::vector<idx> qpp::QCircuit::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

```
7.53.5.30 get_measurement_count()
```

```
idx qpp::QCircuit::get_measurement_count ( ) const [inline], [noexcept]
```

Quantum circuit total measurement count.

Returns

Total measurement count

```
7.53.5.31 get_measurements()
```

```
const std::vector<MeasureStep>& qpp::QCircuit::get_measurements ( ) const [inline], [noexcept]
```

Vector of qpp::QCircuit::MeasureStep.

Returns

Vector of qpp::QCircuit::MeasureStep

```
7.53.5.32 get_name()
```

```
std::string qpp::QCircuit::get_name ( ) const [inline]
```

Quantum circuit name.

Returns

Quantum circuit name

```
7.53.5.33 get_nc()
```

```
idx qpp::QCircuit::get_nc ( ) const [inline], [noexcept]
```

Total number of classical dits in the circuit.

Returns

Total number of classical dits

```
7.53.5.34 get_non_measured()
```

```
std::vector<idx> qpp::QCircuit::get_non_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

Returns

Vector of non-measured qudit indexes

```
7.53.5.35 get_nq()
```

```
idx qpp::QCircuit::get_nq ( ) const [inline], [noexcept]
```

Total number of qudits in the circuit.

Returns

Total number of qudits

7.53.5.36 get_step_count()

```
idx qpp::QCircuit::get_step_count ( ) const [inline], [noexcept]
```

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

Returns

Total (gates + measurements) count

7.53.5.37 measureV() [1/2]

```
QCircuit& qpp::QCircuit::measureV (
            const cmat & V,
             idx target,
             idx c_reg,
             std::string name = "" ) [inline]
```

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V
target	Qudit index
c_reg	Classical register where the value of the measurement is stored
name	Optional measurement name

Returns

Reference to the current instance

7.53.5.38 measureV() [2/2]

```
QCircuit& qpp::QCircuit::measureV (
            const cmat \& V,
             const std::vector< idx > & target,
            idx c_reg,
             std::string name = "" ) [inline]
```

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V	
target	Target qudit indexes that are jointly measured	
c_reg	Classical register where the value of the measurement is stored	
name	Optional measurement name	Generated by I

Doxygen

Returns

Reference to the current instance

7.53.5.39 measureZ()

Measurement of single qudit in the computational basis (Z-basis)

Parameters

target	Qudit index
c_reg	Classical register where the value of the measurement is being stored
name	Optional measurement name, default is "Measure Z"

Returns

Reference to the current instance

7.53.5.40 QFT()

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	get Subsystem indexes where the quantum Fourier transform is appl	
swap	Swaps the qubits at the end (true by default)	

Returns

Reference to the current instance

7.53.5.41 TFQ()

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the inverse quantum Fourier transform is applied	
swap	Swaps the qubits at the end (true by default)	

Returns

Reference to the current instance

7.53.5.42 to_JSON()

qpp::IJOSN::to_JSON() override

Displays the quantum circuit in JSON format

Parameters

enclosed_in_curly_brackets	If true, encloses the result in curly brackets
----------------------------	--

Returns

String containing the JSON representation of the quantum circuit

Implements qpp::IJSON.

7.53.6 Friends And Related Function Documentation

 ${\bf Extraction\ operator\ overload\ for\ qpp::} {\bf QCircuit::} {\bf GateType\ enum\ class.}$

Parameters

os	Output stream
gate_type	qpp::QCircuit::GateType enum class

Returns

Output stream

Extraction operator overload for qpp::QCircuit::GateStep class.

Parameters

os	Output stream
gate_type	qpp::QCircuit::GateStep class

Returns

Output stream

Extraction operator overload for qpp::QCircuit::MeasureType enum class.

Parameters

os	Output stream
gate_type	qpp::QCircuit::MeasureType enum class

Returns

Output stream

Extraction operator overload for qpp::QCircuit::MeasureStep class.

Parameters

os	Output stream
gate_type	qpp::QCircuit::MeasureStep enum class

Returns

Output stream

7.53.7 Member Data Documentation

```
7.53.7.1 d_
const idx qpp::QCircuit::d_ [private]
```

7.53.7.2 gates_

gates

qudit dimension

```
std::vector<GateStep> qpp::QCircuit::gates_ {} [private]
```

7.53.7.3 measured_

```
std::vector<bool> qpp::QCircuit::measured_ [private]
```

keeps track of the measured qudits

7.53.7.4 measurements_

```
std::vector<MeasureStep> qpp::QCircuit::measurements_ {} [private]
```

measurements

```
7.53.7.5 name_
std::string qpp::QCircuit::name_ [private]
optional circuit name
7.53.7.6 nc_
const idx qpp::QCircuit::nc_ [private]
number of classical "dits"
7.53.7.7 nq_
const idx qpp::QCircuit::nq_ [private]
number of qudits
7.53.7.8 step_types_
std::vector<StepType> qpp::QCircuit::step_types_ {} [private]
type of each step
The documentation for this class was generated from the following file:
```

Generated by Doxygen


· classes/circuits.h

7.54 qpp::QEngine Class Reference


Quantum circuit engine, executes qpp::QCircuit.

#include <classes/circuits.h>

Inheritance diagram for qpp::QEngine:



Collaboration diagram for qpp::QEngine:



Public Member Functions

• QEngine (const QCircuit &qcd)

Constructs a quantum engine out of a quantum circuit.

• QEngine (QCircuit &&)=delete

Disables rvalue QCircuit.

virtual ~QEngine ()=default

Default virtual destructor.

• ket get_psi () const

Underlying quantum state.

ket & get_ref_psi ()

Reference to the underlying quantum state.

std::vector< idx > get_dits () const

Vector with the values of the underlying classical dits.

• idx get_dit (idx i) const

Value of the classical dit at position i.

std::vector< double > get_probs () const

Vector of underlying measurement outcome probabilities.

• bool get measured (idx i) const

Check whether qudit i was already measured.

std::vector< idx > get_measured () const

Vector of already measured gudit indexes.

std::vector< idx > get_not_measured () const

Vector of non-measured qudit indexes.

const QCircuit & get_circuit () const noexcept

Quantum circuit.

QEngine & set_dit (idx i, idx value)

Sets the classical dit at position i.

void reset ()

Resets the engine.

• std::ostream & display (std::ostream &os) const override

qpp::IDisplay::display() override

void execute (const QCircuit::iterator::value_type &elem)

Executes one step in the quantum circuit.

void execute (const QCircuit::iterator &it)

Executes one step in the quantum circuit.

std::string to_JSON (bool enclosed_in_curly_brackets=true) const override

qpp::IJOSN::to_JSON() override

Protected Member Functions

void set_measured_ (idx i)

Marks qudit i as measured then re-label accordingly the remaining non-measured qudits.

std::vector< idx > get_relative_pos_ (std::vector< idx > v)

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

Protected Attributes

· const QCircuit & qcd_

quantum circuit

ket psi_

state vector

std::vector< idx > dits_

classical dits

std::vector< double > probs

measurement probabilities

std::vector < idx > subsys_

7.54.1 Detailed Description

Quantum circuit engine, executes qpp::QCircuit.

See also

qpp::QCircuit

7.54.2 Constructor & Destructor Documentation

Constructs a quantum engine out of a quantum circuit.

Note

The quantum circuit must be an Ivalue

See also

```
qpp::QEngine(QCircuit&&)
```

Note

The initial underlying quantum state is set to $|0\rangle^{\otimes n}$

Parameters

```
qcd Quantum circuit
```

```
7.54.2.2 QEngine() [2/2]
```

Disables rvalue QCircuit.

```
7.54.2.3 \sim QEngine()
```

```
virtual qpp::QEngine::~QEngine ( ) [virtual], [default]
```

Default virtual destructor.

7.54.3 Member Function Documentation

7.54.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the state of the engine

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

Executes one step in the quantum circuit.

Parameters

```
elem Step to be executed
```

Executes one step in the quantum circuit.

Parameters

it Iterator to the step to be executed

```
7.54.3.4 get_circuit()
```

```
const QCircuit& qpp::QEngine::get_circuit ( ) const [inline], [noexcept]
```

Quantum circuit.

Returns

Underlying quantum circuit

```
7.54.3.5 get_dit()
```

```
idx qpp::QEngine::get_dit (
        idx i) const [inline]
```

Value of the classical dit at position i.

Parameters

```
i Classical dit index
```

Returns

Value of the classical dit at position i

```
7.54.3.6 get_dits()
```

```
std::vector<idx> qpp::QEngine::get_dits ( ) const [inline]
```

Vector with the values of the underlying classical dits.

Returns

Vector of underlying classical dits

```
7.54.3.7 get_measured() [1/2]
```

```
bool qpp::QEngine::get_measured (
          idx i ) const [inline]
```

Check whether qudit *i* was already measured.

Parameters

i Qudit index

Returns

True if qudit i was already measured, false othwewise

```
7.54.3.8 get_measured() [2/2]
std::vector<idx> qpp::QEngine::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

7.54.3.9 get_not_measured()

```
std::vector<idx> qpp::QEngine::get_not_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

Returns

Vector of non-measured qudit indexes

7.54.3.10 get_probs()

```
std::vector<double> qpp::QEngine::get_probs ( ) const [inline]
```

Vector of underlying measurement outcome probabilities.

Note

The probability vector has the same length as the vector of classical dits. If the measurement result is stored at the index c_reg , then the outcome probability is automatically stored at the same index c_reg in the probability vector.

Returns

Vector of underlying measurement outcome probabilities

```
7.54.3.11 get_psi()
```

```
ket qpp::QEngine::get_psi ( ) const [inline]
```

Underlying quantum state.

Returns

Underlying quantum state

```
7.54.3.12 get_ref_psi()
```

```
ket& qpp::QEngine::get_ref_psi ( ) [inline]
```

Reference to the underlying quantum state.

Returns

Reference to the underlying quantum state

```
7.54.3.13 get_relative_pos_()
```

```
\label{eq:condition} $$ std::vector < idx > qpp::QEngine::get_relative_pos_ ( \\ std::vector < idx > v ) [inline], [protected] $$
```

Giving a vector *V* of non-measured qudits, get their relative position with respect to the measured qudits.

Parameters



Returns

Vector of qudit indexes

7.54.3.14 reset()

```
void qpp::QEngine::reset ( ) [inline]
```

Resets the engine.

Re-initializes everything to zero and sets the initial state to $|0\rangle^{\otimes n}$

7.54.3.15 set_dit()

Sets the classical dit at position i.

Parameters

i	Classical dit index
value	Classical dit value

Returns

Reference to the current instance

7.54.3.16 set_measured_()

```
void qpp::QEngine::set_measured_ (
          idx i ) [inline], [protected]
```

Marks qudit *i* as measured then re-label accordingly the remaining non-measured qudits.

Parameters

i Qudit index

7.54.3.17 to_JSON()

qpp::IJOSN::to_JSON() override

Displays the state of the engine in JSON format

Parameters

enclosed_in_curly_brackets	If true, encloses the result in curly brackets
----------------------------	--

Returns

String containing the JSON representation of the state of the engine

Implements qpp::IJSON.

7.54.4 Member Data Documentation

```
7.54.4.1 dits
std::vector<idx> qpp::QEngine::dits_ [protected]
classical dits
7.54.4.2 probs_
std::vector<double> qpp::QEngine::probs_ [protected]
measurement probabilities
7.54.4.3 psi
ket qpp::QEngine::psi_ [protected]
state vector
7.54.4.4 qcd_
const QCircuit& qpp::QEngine::qcd_ [protected]
quantum circuit
7.54.4.5 subsys_
std::vector<idx> qpp::QEngine::subsys_ [protected]
```

• classes/circuits.h

keeps track of the measured subsystems, relabel them after measurements


The documentation for this class was generated from the following file:

7.55 qpp::QubitAmplitudeDampingNoise Class Reference


Qubit amplitude damping noise, as described in Nielsen and Chuang.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitAmplitudeDampingNoise:



Collaboration diagram for qpp::QubitAmplitudeDampingNoise:



Public Member Functions

• QubitAmplitudeDampingNoise (double gamma)

Qubit amplitude damping noise constructor.

Additional Inherited Members

7.55.1 Detailed Description

Qubit amplitude damping noise, as described in Nielsen and Chuang.

7.55.2 Constructor & Destructor Documentation

7.55.2.1 QubitAmplitudeDampingNoise()

Qubit amplitude damping noise constructor.

Parameters

gamma	Amplitude damping probability
-------	-------------------------------

The documentation for this class was generated from the following file:


classes/noise.h

7.56 qpp::QubitBitFlipNoise Class Reference


Qubit bit flip noise.

```
#include <classes/noise.h>
```

 $Inheritance\ diagram\ for\ qpp:: Qubit Bit Flip Noise:$



Collaboration diagram for qpp::QubitBitFlipNoise:



Public Member Functions

QubitBitFlipNoise (double p)
 Qubit bit flip noise constructor.

Additional Inherited Members

7.56.1 Detailed Description

Qubit bit flip noise.

7.56.2 Constructor & Destructor Documentation

7.56.2.1 QubitBitFlipNoise()

```
\label{eq:qpp::QubitBitFlipNoise} $$ \operatorname{qpp}::\operatorname{QubitBitFlipNoise} ($$ \operatorname{double} p ) [inline], [explicit] $$
```

Qubit bit flip noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.57 qpp::QubitBitPhaseFlipNoise Class Reference


Qubit bit-phase flip (dephasing) noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitBitPhaseFlipNoise:



Collaboration diagram for qpp::QubitBitPhaseFlipNoise:



Public Member Functions

QubitBitPhaseFlipNoise (double p)
 Qubit bit-phase flip noise constructor.

Additional Inherited Members

7.57.1 Detailed Description

Qubit bit-phase flip (dephasing) noise.

7.57.2 Constructor & Destructor Documentation

7.57.2.1 QubitBitPhaseFlipNoise()

```
\label{eq:qpp::QubitBitPhaseFlipNoise::QubitBitPhaseFlipNoise (} \\ \text{double } p \text{ ) } \quad \text{[inline], [explicit]}
```

Qubit bit-phase flip noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.58 qpp::QubitDepolarizingNoise Class Reference


Qubit depolarizing noise.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitDepolarizingNoise:



Collaboration diagram for qpp::QubitDepolarizingNoise:



Public Member Functions

QubitDepolarizingNoise (double p)
 Qubit depolarizing noise constructor.

Additional Inherited Members

7.58.1 Detailed Description

Qubit depolarizing noise.

7.58.2 Constructor & Destructor Documentation

7.58.2.1 QubitDepolarizingNoise()

```
\label{eq:qpp::QubitDepolarizingNoise::QubitDepolarizingNoise (} $$ double $p$ ) [inline], [explicit]
```

Qubit depolarizing noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.59 qpp::QubitPhaseDampingNoise Class Reference


Qubit phase damping noise, as described in Nielsen and Chuang.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitPhaseDampingNoise:



Collaboration diagram for qpp::QubitPhaseDampingNoise:



Public Member Functions

QubitPhaseDampingNoise (double lambda)
 Qubit phase damping noise constructor.

Additional Inherited Members

7.59.1 Detailed Description

Qubit phase damping noise, as described in Nielsen and Chuang.

7.59.2 Constructor & Destructor Documentation

7.59.2.1 QubitPhaseDampingNoise()

Qubit phase damping noise constructor.

Parameters

gamma	Phase damping probability
-------	---------------------------

The documentation for this class was generated from the following file:


· classes/noise.h

7.60 qpp::QubitPhaseFlipNoise Class Reference


Qubit phase flip (dephasing) noise.

```
#include <classes/noise.h>
```

 $Inheritance\ diagram\ for\ qpp::Qubit Phase Flip Noise:$



Collaboration diagram for qpp::QubitPhaseFlipNoise:



Public Member Functions

• QubitPhaseFlipNoise (double p)

Qubit phase flip (dephasing) noise constructor.

Additional Inherited Members

7.60.1 Detailed Description

Qubit phase flip (dephasing) noise.

7.60.2 Constructor & Destructor Documentation

7.60.2.1 QubitPhaseFlipNoise()

Qubit phase flip (dephasing) noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


• classes/noise.h

7.61 qpp::exception::QuditAlreadyMeasured Class Reference


Qudit was already measured exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::QuditAlreadyMeasured:



Collaboration diagram for qpp::exception::QuditAlreadyMeasured:



Public Member Functions

- std::string type_description () const override
 - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.61.1 Detailed Description

Qudit was already measured exception.

The qudit was already measured and cannot be measured again

7.61.2 Member Function Documentation

7.61.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred
--

7.61.2.2 type_description()

std::string qpp::exception::QuditAlreadyMeasured::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.62 qpp::QuditDepolarizingNoise Class Reference


Qudit depolarizing noise.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QuditDepolarizingNoise:



Collaboration diagram for qpp::QuditDepolarizingNoise:



Public Member Functions

QuditDepolarizingNoise (double p, idx d)
 Qudit depolarizing noise constructor.

Private Member Functions

- std::vector< cmat > fill_Ks_ (idx d) const
 - Fills the Kraus operator vector.
- std::vector< double > fill_probs_ (double p, idx d) const
 Fills the probability vector.

Additional Inherited Members

7.62.1 Detailed Description

Qudit depolarizing noise.

7.62.2 Constructor & Destructor Documentation

7.62.2.1 QuditDepolarizingNoise()

```
qpp::QuditDepolarizingNoise::QuditDepolarizingNoise ( double p,  idx \ d \ ) \ \ [inline], \ [explicit]
```

Qudit depolarizing noise constructor.

Parameters

р	Noise probability
d	Subsystem dimension

7.62.3 Member Function Documentation

Fills the Kraus operator vector.

Parameters

d Qudit dimension

Returns

Vector of Kraus operators representing the depolarizing noise

7.62.3.2 fill_probs_()

Fills the probability vector.

Parameters

р	Probability
d	Qudit dimension

Returns

Probability vector

The documentation for this class was generated from the following file:


• classes/noise.h

7.63 qpp::RandomDevices Class Reference


Singleton class that manages the source of randomness in the library.

#include <classes/random_devices.h>

Inheritance diagram for qpp::RandomDevices:



Collaboration diagram for qpp::RandomDevices:



Public Member Functions

• std::mt19937 & get_prng ()

Returns a reference to the internal PRNG object.

std::istream & load (std::istream &is)

Loads the state of the PRNG from an input stream.

• std::ostream & save (std::ostream &os) const

Saves the state of the PRNG to an output stream.

Private Member Functions

• RandomDevices ()

Initializes and seeds the random number generators.

∼RandomDevices ()=default

Default destructor.

Private Attributes

 std::random_device rd_ used to seed std::mt19937 prng_

std::mt19937 prng_

Mersenne twister random number generator.

Friends

class internal::Singleton < RandomDevices >

Additional Inherited Members

7.63.1 Detailed Description

Singleton class that manages the source of randomness in the library.

Warning

This class DOES NOT seed the standard C number generator used by Eigen::Matrix::Random(), since it is not thread safe. Do not use Eigen::Matrix::Random() or functions that depend on the C style random number engine, but use qpp::rand() instead!

7.63.2 Constructor & Destructor Documentation

7.63.2.1 RandomDevices()

```
qpp::RandomDevices::RandomDevices ( ) [inline], [private]
```

Initializes and seeds the random number generators.

7.63.2.2 ∼RandomDevices()

```
\verb"qpp::RandomDevices::$\sim$RandomDevices ( ) [private], [default]
```

Default destructor.

7.63.3 Member Function Documentation

```
7.63.3.1 get_prng()
```

```
std::mt19937& qpp::RandomDevices::get_prng ( ) [inline]
```

Returns a reference to the internal PRNG object.

Returns

Reference to the internal PRNG object

7.63.3.2 load()

Loads the state of the PRNG from an input stream.

Parameters

```
is Input stream
```

Returns

The input stream

7.63.3.3 save()

Saves the state of the PRNG to an output stream.

Parameters

os Output stream

Returns

The output stream

7.63.4 Friends And Related Function Documentation

```
7.63.4.1 internal::Singleton < RandomDevices >
```

```
friend class internal::Singleton< RandomDevices > [friend]
```

7.63.5 Member Data Documentation

```
7.63.5.1 prng_
```

```
std::mt19937 qpp::RandomDevices::prng_ [private]
```

Mersenne twister random number generator.

```
7.63.5.2 rd_
```

```
std::random_device qpp::RandomDevices::rd_ [private]
```

used to seed std::mt19937 prng_

The documentation for this class was generated from the following file:

• classes/random_devices.h

7.64 qpp::internal::Singleton < T > Class Template Reference

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

```
#include <internal/classes/singleton.h>
```

Static Public Member Functions

- static T & get_instance () noexcept(std::is_nothrow_constructible < T >::value)
- static T & get_thread_local_instance () noexcept(std::is_nothrow_constructible < T >::value)

Protected Member Functions

- Singleton () noexcept=default
- Singleton (const Singleton &)=delete
- Singleton & operator= (const Singleton &)=delete
- virtual ∼Singleton ()=default

7.64.1 Detailed Description

```
template<typename T>
class qpp::internal::Singleton< T>
```

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

To implement a singleton, derive your class from qpp::internal::Singleton, make qpp::internal::Singleton a friend of your class, then declare the constructor and destructor of your class as private. To get an instance, use the static member function qpp::internal::Singleton::get_instance() (qpp::internal::Singleton::get_thread_local_instance()), which returns a reference (thread_local_reference) to your newly created singleton (thread-safe in C++11).

Example:

See also

Code of qpp::Codes, qpp::Gates, qpp::Init, qpp::RandomDevices, qpp::States or qpp.h for real world examples of usage.

7.64.2 Constructor & Destructor Documentation

```
7.64.2.1 Singleton() [1/2]
template<typename T>
qpp::internal::Singleton < T >::Singleton ( ) [protected], [default], [noexcept]
7.64.2.2 Singleton() [2/2]
template<typename T>
qpp::internal::Singleton < T >::Singleton (
            const Singleton< T > \& ) [protected], [delete]
7.64.2.3 ∼Singleton()
template<typename T>
virtual qpp::internal::Singleton < T >::~Singleton ( ) [protected], [virtual], [default]
7.64.3 Member Function Documentation
7.64.3.1 get_instance()
template<typename T>
static T& qpp::internal::Singleton< T >::get_instance ( ) [inline], [static], [noexcept]
7.64.3.2 get_thread_local_instance()
template<typename T>
static T& qpp::internal::Singleton< T >::get_thread_local_instance ( ) [inline], [static],
[noexcept]
7.64.3.3 operator=()
template<typename T>
Singleton& qpp::internal::Singleton< T >::operator= (
             const Singleton< T > \& ) [protected], [delete]
```

The documentation for this class was generated from the following file:


• internal/classes/singleton.h

7.65 qpp::exception::SizeMismatch Class Reference

Size mismatch exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SizeMismatch:



Collaboration diagram for qpp::exception::SizeMismatch:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.65.1 Detailed Description

Size mismatch exception.

Sizes do not match

7.65.2 Member Function Documentation

7.65.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.65.2.2 type_description()

std::string qpp::exception::SizeMismatch::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

7.66 qpp::NoiseType::StateDependent Class Reference

Template tag, used whenever the noise is state-dependent.

#include <classes/noise.h>

7.66.1 Detailed Description

Template tag, used whenever the noise is state-dependent.

The documentation for this class was generated from the following file:

· classes/noise.h

7.67 qpp::NoiseType::StateIndependent Class Reference

Template tag, used whenever the noise is state-independent.

#include <classes/noise.h>

7.67.1 Detailed Description

Template tag, used whenever the noise is state-independent.

The documentation for this class was generated from the following file:


classes/noise.h

7.68 qpp::States Class Reference


const Singleton class that implements most commonly used states

#include <classes/states.h>

Inheritance diagram for qpp::States:



Collaboration diagram for qpp::States:



Public Member Functions

• ket mes (idx d=2) const

Maximally entangled state of 2 qudits.

• ket zero (idx n, idx d=2) const

Zero state of n qudits.

• ket one (idx n, idx d=2) const

One state of n qudits.

• ket jn (idx j, idx n, idx d=2) const

 $|j\rangle^{\otimes n}$ state of n qudits

• ket plus (idx n) const

Plus state of n qubits.

• ket minus (idx n) const

Minus state of n qubits.

Public Attributes

```
    ket x0 {ket::Zero(2)}
```

Pauli Sigma-X 0-eigenstate |+>

ket x1 {ket::Zero(2)}

Pauli Sigma-X 1-eigenstate |->

ket y0 {ket::Zero(2)}

Pauli Sigma-Y 0-eigenstate |y+>

ket y1 {ket::Zero(2)}

Pauli Sigma-Y 1-eigenstate | y->

ket z0 {ket::Zero(2)}

Pauli Sigma-Z 0-eigenstate | 0>

ket z1 {ket::Zero(2)}

Pauli Sigma-Z 1-eigenstate | 1>

• cmat px0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

• cmat px1 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.

```
    cmat py0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 0-eigenstate |y+\rangle < y+|.

    cmat py1 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.

    cmat pz0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
• cmat pz1 {cmat::Zero(2, 2)}
      Projector onto the Pauli Sigma-Z 1-eigenstate |1><1|.
ket b00 {ket::Zero(4)}
      Bell-00 state, as described in Nielsen and Chuang.

    ket b01 {ket::Zero(4)}

      Bell-01 state, as described in Nielsen and Chuang.

    ket b10 {ket::Zero(4)}

      Bell-10 state, as described in Nielsen and Chuang.
ket b11 {ket::Zero(4)}
      Bell-11 state, as described in Nielsen and Chuang.

    cmat pb00 {cmat::Zero(4, 4)}

      Projector onto the Bell-00 state.

    cmat pb01 {cmat::Zero(4, 4)}

      Projector onto the Bell-01 state.

    cmat pb10 {cmat::Zero(4, 4)}

      Projector onto the Bell-10 state.

    cmat pb11 {cmat::Zero(4, 4)}

      Projector onto the Bell-11 state.
ket GHZ {ket::Zero(8)}
      GHZ state.

    ket W {ket::Zero(8)}

      W state.
cmat pGHZ {cmat::Zero(8, 8)}
      Projector onto the GHZ state.
cmat pW {cmat::Zero(8, 8)}
      Projector onto the W state.
```

Private Member Functions

- States ()
- ∼States ()=default

Default destructor.

Friends

class internal::Singleton < const States >

Additional Inherited Members

7.68.1 Detailed Description

const Singleton class that implements most commonly used states

7.68.2 Constructor & Destructor Documentation

```
7.68.2.1 States()

qpp::States::States ( ) [inline], [private]

Initialize the states

7.68.2.2 ~States()

qpp::States::~States ( ) [private], [default]
```

7.68.3 Member Function Documentation

```
7.68.3.1 jn()
```

Default destructor.

 $|j\rangle^{\otimes n}$ state of *n* qudits

Parameters

j	Non-negative integer
n	Non-negative integer
d	Subsystem dimensions

Returns

 $|j\rangle^{\otimes n}$ state of *n* qudits

7.68.3.2 mes()

```
ket qpp::States::mes (
idx d = 2 ) const [inline]
```

Maximally entangled state of 2 qudits.

Parameters

d Subsystem dimensions

Returns

Maximally entangled state $\frac{1}{\sqrt{d}} \sum_{j=0}^{d-1} |jj\rangle$ of 2 qudits

7.68.3.3 minus()

```
ket qpp::States::minus (
          idx n ) const [inline]
```

Minus state of n qubits.

Parameters

n Non-negative integer

Returns

Minus state $|-\rangle^{\otimes n}$ of n qubits

7.68.3.4 one()

```
ket qpp::States::one (
        idx n,
        idx d = 2 ) const [inline]
```

One state of *n* qudits.

Parameters

n	Non-negative integer
d	Subsystem dimensions

Returns

One state $|1\rangle^{\otimes n}$ of n qudits

7.68.3.5 plus()

```
ket qpp::States::plus (
         idx n ) const [inline]
```

Plus state of *n* qubits.

Parameters

```
n Non-negative integer
```

Returns

Plus state $|+\rangle^{\otimes n}$ of n qubits

7.68.3.6 zero()

```
ket qpp::States::zero (
         idx n,
         idx d = 2 ) const [inline]
```

Zero state of *n* qudits.

Parameters

n	Non-negative integer
d	Subsystem dimensions

Returns

Zero state $|0\rangle^{\otimes n}$ of n qudits

7.68.4 Friends And Related Function Documentation

```
7.68.4.1 internal::Singleton < const States >
friend class internal::Singleton < const States > [friend]
```

7.68.5 Member Data Documentation

```
7.68.5.1 b00
```

```
ket qpp::States::b00 {ket::Zero(4)}
```

Bell-00 state, as described in Nielsen and Chuang.

```
7.68.5.2 b01
```

```
ket qpp::States::b01 {ket::Zero(4)}
```

Bell-01 state, as described in Nielsen and Chuang.

```
7.68.5.3 b10
```

```
ket qpp::States::b10 {ket::Zero(4)}
```

Bell-10 state, as described in Nielsen and Chuang.

7.68.5.4 b11

```
ket qpp::States::b11 {ket::Zero(4)}
```

Bell-11 state, as described in Nielsen and Chuang.

7.68.5.5 GHZ

```
ket qpp::States::GHZ {ket::Zero(8)}
```

GHZ state.

7.68.5.6 pb00

```
cmat qpp::States::pb00 {cmat::Zero(4, 4)}
```

Projector onto the Bell-00 state.

```
7.68.5.7 pb01
cmat qpp::States::pb01 {cmat::Zero(4, 4)}
Projector onto the Bell-01 state.
7.68.5.8 pb10
cmat qpp::States::pb10 {cmat::Zero(4, 4)}
Projector onto the Bell-10 state.
7.68.5.9 pb11
cmat qpp::States::pb11 {cmat::Zero(4, 4)}
Projector onto the Bell-11 state.
7.68.5.10 pGHZ
cmat qpp::States::pGHZ {cmat::Zero(8, 8)}
Projector onto the GHZ state.
7.68.5.11 pW
cmat qpp::States::pW {cmat::Zero(8, 8)}
Projector onto the W state.
7.68.5.12 px0
cmat qpp::States::px0 {cmat::Zero(2, 2)}
```

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

```
7.68.5.13 px1
cmat qpp::States::px1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.
7.68.5.14 py0
cmat qpp::States::py0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 0-eigenstate |y+>< y+|.
7.68.5.15 py1
cmat qpp::States::py1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.
7.68.5.16 pz0
cmat qpp::States::pz0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
7.68.5.17 pz1
cmat qpp::States::pz1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 1-eigenstate |1><1|.
7.68.5.18 W
ket qpp::States::W {ket::Zero(8)}
W state.
```

```
7.68.5.19 x0
ket qpp::States::x0 {ket::Zero(2)}
Pauli Sigma-X 0-eigenstate |+>
7.68.5.20 x1
ket qpp::States::x1 {ket::Zero(2)}
Pauli Sigma-X 1-eigenstate |->
7.68.5.21 y0
ket qpp::States::y0 {ket::Zero(2)}
Pauli Sigma-Y 0-eigenstate |y+>
7.68.5.22 y1
ket qpp::States::y1 {ket::Zero(2)}
Pauli Sigma-Y 1-eigenstate |y->
7.68.5.23 z0
ket qpp::States::z0 {ket::Zero(2)}
Pauli Sigma-Z 0-eigenstate |0>
7.68.5.24 z1
ket qpp::States::z1 {ket::Zero(2)}
Pauli Sigma-Z 1-eigenstate |1>
The documentation for this class was generated from the following file:
```


classes/states.h

7.69 qpp::exception::SubsysMismatchDims Class Reference


Subsystems mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SubsysMismatchDims:



Collaboration diagram for qpp::exception::SubsysMismatchDims:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.69.1 Detailed Description

Subsystems mismatch dimensions exception.

std::vector<idx> of subsystem labels has duplicates, or has entries that are larger than the size of the std← ::vector<idx> of dimensions

7.69.2 Member Function Documentation

7.69.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the exception occurred
--

7.69.2.2 type_description()

```
std::string qpp::exception::SubsysMismatchDims::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.70 qpp::Timer < T, CLOCK_T > Class Template Reference


Chronometer.

#include <classes/timer.h>

Inheritance diagram for qpp::Timer< T, CLOCK_T >:



Collaboration diagram for qpp::Timer < T, CLOCK_T >:



Public Member Functions

· Timer () noexcept

Constructs an instance with the current time as the starting point.

· void tic () noexcept

Resets the chronometer.

• const Timer & toc () noexcept

Stops the chronometer.

· double tics () const noexcept

Time passed in the duration specified by T.

• template<typename U = T>

U get_duration () const noexcept

Duration specified by U.

• Timer (const Timer &)=default

Default copy constructor.

• Timer (Timer &&)=default

Default move constructor.

• Timer & operator= (const Timer &)=default

Default copy assignment operator.

• Timer & operator= (Timer &&)=default

Default move assignment operator.

virtual ∼Timer ()=default

Default virtual destructor.

Protected Attributes

- CLOCK_T::time_point start_
- CLOCK_T::time_point end

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display() override*

7.70.1 Detailed Description

```
template < typename\ T = std::chrono::duration < double >, typename\ CLOCK\_T = std::chrono::steady\_clock > class\ qpp::Timer < T,\ CLOCK\_T >
```

Chronometer.

Template Parameters

T	Tics duration, default is std::chrono::duration <double, 1="">, i.e. seconds in double precision</double,>
CLOCK← T	Clock's type, default is std::chrono::steady_clock, not affected by wall clock changes during runtime

7.70.2 Constructor & Destructor Documentation

```
7.70.2.1 Timer() [1/3]
```

```
\label{template} $$ \ensuremath{\texttt{template}}$ $$ \ensuremath{\texttt{T}} = \ensuremath{\texttt{std}}$ : chrono::steady $$ $$ $$ $$ \ensuremath{\texttt{clock}}$ $$ $$ \ensuremath{\texttt{qpp}}$ ::Timer ( ) [inline], [noexcept] $$
```

Constructs an instance with the current time as the starting point.

7.70.2.2 Timer() [2/3]

Default copy constructor.

7.70.2.3 Timer() [3/3]

Default move constructor.

7.70.2.4 \sim Timer()

```
\label{template} $$ \ensuremath{\sf template}$ $$ \ensurem
```

Default virtual destructor.

7.70.3 Member Function Documentation

7.70.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream the number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc().

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.70.3.2 get_duration()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
template<typename U = T>
U qpp::Timer< T, CLOCK_T >::get_duration ( ) const [inline], [noexcept]
```

Duration specified by U.

Template Parameters

U Duration, default is T, which defaults to std::chrono::duration<double, 1>, i.e. seconds in double precision

Returns

Duration that passed between the instantiation/reset and invocation of qpp::Timer::toc()

```
7.70.3.3 operator=() [1/2]
```

Default copy assignment operator.

```
7.70.3.4 operator=() [2/2]
```

Default move assignment operator.

7.70.3.5 tic()

Resets the chronometer.

Resets the starting/ending point to the current time

7.70.3.6 tics()

```
 \begin{tabular}{ll} template < typename T = std::chrono::duration < double >, typename CLOCK_T = std::chrono::steady \leftarrow \_clock > \\ double qpp::Timer < T, CLOCK_T >::tics ( ) const [inline], [noexcept] \\ \end{tabular}
```

Time passed in the duration specified by T.

Returns

Number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc()

7.70.3.7 toc()

```
\label{lock-type-ame} $$ $$ template<typename T = std::chrono::steady \leftarrow \_clock> $$ const Timer& qpp::Timer< T, CLOCK_T >::toc ( ) [inline], [noexcept] $$
```

Stops the chronometer.

Set the current time as the ending point

Returns

Reference to the current instance

7.70.4 Member Data Documentation

7.70.4.1 end

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady←
   _clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::end_ [protected]
```

7.70.4.2 start_

```
\label{lock_typename} $$ $$ template < typename $$ CLOCK_T = std::chrono::steady \hookrightarrow \_clock > $$ CLOCK_T::time\_point $$ qpp::Timer < T, CLOCK_T >::start_ [protected] $$
```

The documentation for this class was generated from the following file:


· classes/timer.h

7.71 qpp::exception::TypeMismatch Class Reference


Type mismatch exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::TypeMismatch:



Collaboration diagram for qpp::exception::TypeMismatch:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.71.1 Detailed Description

Type mismatch exception.

Scalar types do not match

7.71.2 Member Function Documentation

7.71.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.71.2.2 type_description()

std::string qpp::exception::TypeMismatch::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.72 qpp::exception::UndefinedType Class Reference


Not defined for this type exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::UndefinedType:



Collaboration diagram for qpp::exception::UndefinedType:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.72.1 Detailed Description

Not defined for this type exception.

Templated specialization is not defined for this type

7.72.2 Member Function Documentation

7.72.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred	1
-------	--	---

7.72.2.2 type_description()

std::string qpp::exception::UndefinedType::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


• classes/exception.h

7.73 qpp::exception::Unknown Class Reference


Unknown exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Unknown:



Collaboration diagram for qpp::exception::Unknown:



Public Member Functions

- std::string type_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

7.73.1 Detailed Description

Unknown exception.

Thrown when no other exception is suitable (not recommended, it is better to define another suitable exception type)

7.73.2 Member Function Documentation

7.73.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

7.73.2.2 type_description()

std::string qpp::exception::Unknown::type_description () const [inline], [override], [virtual]

Exception type description.

Returns

Exception type description


Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.74 qpp::QCircuit::iterator::value_type_ Struct Reference

Inheritance diagram for qpp::QCircuit::iterator::value_type_:



Collaboration diagram for qpp::QCircuit::iterator::value_type_:



Public Member Functions

```
    value_type_ (const QCircuit *value_type_qcd)
        Default value_type_ constructor.
    value_type_ (const value_type_ &)=default
        Default copy constructor.
    value_type_ & operator= (const value_type_ &)=default
        Default copy assignment operator.
```

std::ostream & display (std::ostream &os) const override

qpp::IDisplay::display() override

Public Attributes

```
    const QCircuit * value_type_qcd_
    < non-owning pointer to the parent iterator</li>
```

StepType type_{StepType::NONE}

step type

idx ip_ {idx_infty}

instruction pointer

std::vector < GateStep >::const_iterator gates_ip_ {}
 gates instruction pointer

std::vector < MeasureStep >::const_iterator measurements_ip_{}{}
 measurements instruction pointer

7.74.1 Constructor & Destructor Documentation

Default value_type_ constructor.

Parameters

```
value_type_qcd | Constant pointer to quantum circuit
```

Default copy constructor.

7.74.2 Member Function Documentation

7.74.2.1 display()

qpp::IDisplay::display() override

Writes to the output stream the textual representation of the iterator de-referenced element

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.74.2.2 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

7.74.3 Member Data Documentation

```
7.74.3.1 gates_ip_
```

```
std::vector<GateStep>::const_iterator qpp::QCircuit::iterator::value_type_::gates_ip_ {}
```

gates instruction pointer

```
7.74.3.2 ip_
idx qpp::QCircuit::iterator::value_type_::ip_ {idx_infty}
instruction pointer
7.74.3.3 measurements_ip_
\verb|std::vector<| MeasureStep| > ::const_iterator | qpp::QCircuit::iterator::value_type_::measurements\_{\leftarrow}| | qpp::QCircuit::qt_iterator::value_type_::qt_iterator::value_type_::qt_iterator::value_type_::qt_iterator::value_type_::qt_iterator::value_type_::qt_iterator::value_type_::qt_iterator::value_type_:
ip_ {}
measurements instruction pointer
7.74.3.4 type_
StepType qpp::QCircuit::iterator::value_type_::type_ {StepType::NONE}
step type
7.74.3.5 value_type_qcd_
const QCircuit* qpp::QCircuit::iterator::value_type_::value_type_qcd_
 < non-owning pointer to the parent iterator
The documentation for this struct was generated from the following file:
```

Generated by Doxygen


· classes/circuits.h

7.75 qpp::exception::ZeroSize Class Reference


Object has zero size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::ZeroSize:



Collaboration diagram for qpp::exception::ZeroSize:



Public Member Functions

• std::string type_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

7.75.1 Detailed Description

Object has zero size exception.

Zero sized object, e.g. empty Eigen::Matrix or std::vector with no elements

7.75.2 Member Function Documentation

7.75.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.75.2.2 type_description()

std::string qpp::exception::ZeroSize::type_description () const [inline], [override], [virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h


Chapter 8

File Documentation

8.1 classes/circuits.h File Reference

Support for qudit quantum circuits.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::QCircuit

Quantum circuit class.

• struct qpp::QCircuit::GateStep

One step consisting only of gates/operators in the circuit.

struct qpp::QCircuit::MeasureStep

One step consisting only of measurements in the circuit.

· class qpp::QCircuit::iterator

Quantum circuit bound-checking (safe) iterator.

- struct qpp::QCircuit::iterator::value_type_
- class qpp::QEngine

Quantum circuit engine, executes qpp::QCircuit.

354 File Documentation

Namespaces

• qpp

Quantum++ main namespace.


8.1.1 Detailed Description

Support for qudit quantum circuits.

8.2 classes/codes.h File Reference

Quantum error correcting codes.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::Codes

const Singleton class that defines quantum error correcting codes

Namespaces

• qpp

Quantum++ main namespace.


8.2.1 Detailed Description

Quantum error correcting codes.

8.3 classes/exception.h File Reference

Exceptions.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::exception::Exception

Base class for generating Quantum++ custom exceptions.

· class qpp::exception::Unknown

Unknown exception.

class qpp::exception::ZeroSize

Object has zero size exception.

• class qpp::exception::MatrixNotSquare

Matrix is not square exception.

class qpp::exception::MatrixNotCvector

Matrix is not a column vector exception.

· class qpp::exception::MatrixNotRvector

Matrix is not a row vector exception.

class qpp::exception::MatrixNotVector

Matrix is not a vector exception.

class qpp::exception::MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

• class qpp::exception::MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

· class qpp::exception::MatrixNotSquareNorVector

Matrix is not square nor vector exception.

class qpp::exception::MatrixMismatchSubsys

Matrix mismatch subsystems exception.

· class qpp::exception::DimsInvalid

Invalid dimension(s) exception.

class qpp::exception::DimsNotEqual

Dimensions not equal exception.

class qpp::exception::DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

class qpp::exception::DimsMismatchCvector

356 File Documentation

Dimension(s) mismatch column vector size exception.

· class qpp::exception::DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

· class qpp::exception::DimsMismatchVector

Dimension(s) mismatch vector size exception.

class qpp::exception::SubsysMismatchDims

Subsystems mismatch dimensions exception.

· class qpp::exception::PermInvalid

Invalid permutation exception.

class qpp::exception::PermMismatchDims

Permutation mismatch dimensions exception.

· class qpp::exception::NotQubitMatrix

Matrix is not 2 x 2 exception.

class qpp::exception::NotQubitCvector

Column vector is not 2 x 1 exception.

· class qpp::exception::NotQubitRvector

Row vector is not 1 x 2 exception.

· class qpp::exception::NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

• class qpp::exception::NotQubitSubsys

Subsystems are not qubits exception.

class gpp::exception::NotBipartite

Not bi-partite exception.

· class qpp::exception::NoCodeword

Codeword does not exist exception.

· class qpp::exception::OutOfRange

Argument out of range exception.

· class qpp::exception::TypeMismatch

Type mismatch exception.

class qpp::exception::SizeMismatch

Size mismatch exception.

class qpp::exception::UndefinedType

Not defined for this type exception.

· class qpp::exception::QuditAlreadyMeasured

Qudit was already measured exception.

· class qpp::exception::Duplicates

System (e.g. std::vector) has duplicates exception.

· class qpp::exception::CustomException

Custom exception.

· class qpp::exception::NotImplemented

Code not yet implemented.

· class qpp::exception::InvalidIterator

Invalid iterator.

Namespaces

qpp

Quantum++ main namespace.

qpp::exception

Quantum++ exception hierarchy namespace.


8.3.1 Detailed Description

Exceptions.

8.4 classes/gates.h File Reference

Quantum gates.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::Gates

const Singleton class that implements most commonly used gates

Namespaces

• qpp

Quantum++ main namespace.

8.4.1 Detailed Description


Quantum gates.

358 File Documentation

8.5 classes/idisplay.h File Reference

Display interface via the non-virtual interface (NVI) and very basic JSON serialization support interface.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

class qpp::IJSON

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

Namespaces

• qpp

Quantum++ main namespace.


8.5.1 Detailed Description

Display interface via the non-virtual interface (NVI) and very basic JSON serialization support interface.

8.6 classes/init.h File Reference

Initialization.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::Init

const Singleton class that performs additional initializations/cleanups

Namespaces

• qpp

Quantum++ main namespace.


8.6.1 Detailed Description

Initialization.

8.7 classes/noise.h File Reference

Noise models.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::NoiseType

Contains template tags used to specify the noise type.

class qpp::NoiseBase< T >

Base class for all noise models, derive your particular noise model.

class qpp::QubitDepolarizingNoise

Qubit depolarizing noise.

· class qpp::QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

• class qpp::QubitBitFlipNoise

Qubit bit flip noise.

· class qpp::QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

· class qpp::QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

· class qpp::QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

· class qpp::QuditDepolarizingNoise

Qudit depolarizing noise.

360 File Documentation

Namespaces

• qpp

Quantum++ main namespace.


8.7.1 Detailed Description

Noise models.

8.8 classes/random_devices.h File Reference

Random devices.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::RandomDevices

Singleton class that manages the source of randomness in the library.

Namespaces

• qpp

Quantum++ main namespace.


8.8.1 Detailed Description

Random devices.

8.9 classes/reversible.h File Reference

Support for classical reversible circuits.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::Dynamic_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

class qpp::Bit_circuit

Classical reversible circuit simulator.

• struct qpp::Bit_circuit::Gate_count

Namespaces

qpp

Quantum++ main namespace.


8.9.1 Detailed Description

Support for classical reversible circuits.

8.10 classes/states.h File Reference

Quantum states.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::States

const Singleton class that implements most commonly used states

Namespaces

• qpp

Quantum++ main namespace.


8.10.1 Detailed Description

Quantum states.

8.11 classes/timer.h File Reference

Timing.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::Timer < T, CLOCK_T >
 Chronometer.

Namespaces

• qpp

Quantum++ main namespace.


8.11.1 Detailed Description

Timing.

8.12 constants.h File Reference

Constants.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

• qpp::literals

Functions

- constexpr cplx qpp::literals::operator"" _i (unsigned long long int x) noexcept
- $\textit{User-defined literal for complex } i = \sqrt{-1} \; \textit{(integer overload)} \\ \bullet \; \textit{constexpr cplx qpp::operator} \\ \text{"} \; \underline{-i} \; \textit{(long double x) noexcept} \\$

User-defined literal for complex $i = \sqrt{-1}$ (real overload)

• cplx qpp::omega (idx D)

D-th root of unity.

Variables

• constexpr double qpp::chop = 1e-10

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

constexpr double qpp::eps = std::numeric_limits<double>::epsilon()

Used to decide whether a number or expression in double precision is zero or not for the purpose of a specific computation.

• constexpr idx qpp::maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

• constexpr double qpp::pi = 3.141592653589793238462643383279502884

• constexpr double qpp::ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

constexpr double qpp::infty = std::numeric_limits<double>::max()

Used to denote infinity in double precision.

• const idx qpp::idx_infty = static_cast<idx>(-1)

Used to denote the largest unsigned index.


8.12.1 Detailed Description

Constants.

8.13 entanglement.h File Reference

Entanglement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

```
template<typename Derived >
  dyn col vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector<
  idx > &dims)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  dyn_col_vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  cmat qpp::schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat qpp::schmidtA (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Bob side.
template<typename Derived >
  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Bob side.
• template<typename Derived >
  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx
  > &dims)
      Schmidt probabilities of the bi-partite pure state A.

    template<typename Derived >

  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt probabilities of the bi-partite pure state A.
• template<typename Derived >
  double qpp::entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Entanglement of the bi-partite pure state A.
• template<typename Derived >
  double <a href="mailto:qpp::entanglement">qpp::entanglement</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Entanglement of the bi-partite pure state A.

    template<typename Derived >

  double <a href="mailto:qpp::gconcurrence">qpp::gconcurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      G-concurrence of the bi-partite pure state A.

    template<typename Derived >

  double qpp::negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double <a href="mailto:qpp::negativity">qpp::negativity</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double <a href="mailto:qpp::concurrence">qpp::concurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.
```


8.13.1 Detailed Description

Entanglement functions.

8.14 entropies.h File Reference

Entropy functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

```
    template < typename Derived >
        double qpp::entropy (const Eigen::MatrixBase < Derived > &A)
```

von-Neumann entropy of the density matrix A

double qpp::entropy (const std::vector< double > &prob)

Shannon entropy of the probability distribution prob.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

```
double <a href="mailto:qpp::renyi">qpp::renyi</a> (const Eigen::MatrixBase< Derived > &A, double alpha)
```

Renyi- α entropy of the density matrix A, for $\alpha \geq 0$.

double qpp::renyi (const std::vector< double > &prob, double alpha)

Renyi- α entropy of the probability distribution prob, for $\alpha \geq 0.$

• template<typename Derived >

```
double <a href="mailto:qpp::tsallis">qpp::tsallis</a> (const Eigen::MatrixBase< Derived > &A, double q)
```

Tsallis- q entropy of the density matrix A, for $q \geq 0$.

double qpp::tsallis (const std::vector< double > &prob, double q)

Tsallis- q entropy of the probability distribution prob, for $q \geq 0$.

• template<typename Derived >

double qpp::qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const std::vector< idx > &subsysB, const std::vector< idx > &dims)

Quantum mutual information between 2 subsystems of a composite system.

• template<typename Derived >

 $\label{lem:double qpp::qmutualinfo} $$ double qpp::qmutualinfo (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &subsysA, const std::vector < idx > &subsysB, idx d=2) \\$

Quantum mutual information between 2 subsystems of a composite system.

8.14.1 Detailed Description

Entropy functions.

8.15 experimental/experimental.h File Reference

Experimental/test functions/classes.

Namespaces

• qpp

Quantum++ main namespace.

· qpp::experimental

Experimental/test functions/classes, do not use or modify.


8.15.1 Detailed Description

Experimental/test functions/classes.

8.16 functions.h File Reference

Generic quantum computing functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

· qpp::literals

Functions

```
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::transpose (const Eigen::MatrixBase< Derived > &A)
• template<typename Derived >
  dyn mat< typename Derived::Scalar > qpp::conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::adjoint (const Eigen::MatrixBase< Derived > &A)
      Adjoint.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::inverse (const Eigen::MatrixBase< Derived > &A)
      Inverse.

    template<typename Derived >

  Derived::Scalar qpp::trace (const Eigen::MatrixBase < Derived > &A)
• template<typename Derived >
  Derived::Scalar <a href="mailto:qpp::det">qpp::det</a> (const Eigen::MatrixBase</a> Derived > &A)

    template<typename Derived >

  Derived::Scalar qpp::logdet (const Eigen::MatrixBase< Derived > &A)
     Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar <a href="mailto:qpp::sum">qpp::sum</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise sum of A.
template<typename Derived >
  Derived::Scalar <a href="mailto:open:prod">open:prod</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise product of A.

    template<typename Derived >

  double <a href="mailto:qpp::norm">qpp::norm</a> (const Eigen::MatrixBase< Derived > &A)
      Frobenius norm.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::normalize (const Eigen::MatrixBase< Derived > &A)
      Normalizes state vector (column or row vector) or density matrix.
• template<typename Derived >
  std::pair< dyn_col_vect< cplx >, cmat > qpp::eig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition.
• template<typename Derived >
  dyn_col_vect< cplx > qpp::evals (const Eigen::MatrixBase< Derived > &A)
     Eigenvalues.

    template<typename Derived >

  cmat qpp::evects (const Eigen::MatrixBase< Derived > &A)
      Eigenvectors.

    template<typename Derived >

  std::pair< dyn_col_vect< double >, cmat > qpp::heig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > qpp::hevals (const Eigen::MatrixBase< Derived > &A)
      Hermitian eigenvalues.
• template<typename Derived >
  cmat qpp::hevects (const Eigen::MatrixBase< Derived > &A)
      Eigenvectors of Hermitian matrix.
```

```
• template<typename Derived >
  std::tuple< cmat, dyn_col_vect< double >, cmat > qpp::svd (const Eigen::MatrixBase< Derived > &A)
     Full singular value decomposition.

    template<typename Derived >

  dyn_col_vect< double > qpp::svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.
• template<typename Derived >
  cmat qpp::svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.

    template<typename Derived >

  cmat qpp::svdV (const Eigen::MatrixBase< Derived > &A)
     Right singular vectors.

    template<typename Derived >

  cmat qpp::funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)

    template < typename Derived >

  cmat qpp::sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.
• template<typename Derived >
  cmat qpp::absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.

    template<typename Derived >

  cmat qpp::expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.
• template<typename Derived >
  cmat qpp::logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.
• template<typename Derived >
  cmat <a href="mailto:qpp::sinm">qpp::sinm</a> (const Eigen::MatrixBase</a> Derived > &A)
     Matrix sin.
• template<typename Derived >
  cmat qpp::cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.
• template<typename Derived >
  cmat qpp::spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::powm (const Eigen::MatrixBase< Derived > &A, idx n)
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

    template<typename Derived >

  double qpp::schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > qpp::cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const
  typename Derived::Scalar &))
     Functor.

    template<typename T >

  dyn_mat< typename T::Scalar > qpp::kron (const T &head)
     Kronecker product.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > qpp::kron (const T &head, const Args &... tail)
     Kronecker product.
```

```
    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::kron (const std::vector< Derived > &As)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::kron (const std::initializer list< Derived > &As)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Kronecker power.
• template<typename T >
  dyn_mat< typename T::Scalar > qpp::dirsum (const T &head)
     Direct sum.
• template<typename T , typename... Args>
  dyn mat< typename T::Scalar > qpp::dirsum (const T &head, const Args &... tail)
     Direct sum.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::vector< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::initializer_list< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::reshape (const Eigen::MatrixBase< Derived > &A, idx rows,
  idx cols)
     Reshape.

    template < typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > qpp::comm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Commutator.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > qpp::anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::prj (const Eigen::MatrixBase< Derived > &A)
     Projector.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::grams (const std::vector< Derived > &As)
     Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::grams (const std::initializer list< Derived > &As)
     Gram-Schmidt orthogonalization.
• template<typename Derived >
  dyn mat< typename Derived::Scalar > qpp::grams (const Eigen::MatrixBase< Derived > &A)
     Gram-Schmidt orthogonalization.

    std::vector< idx > qpp::n2multiidx (idx n, const std::vector< idx > &dims)

     Non-negative integer index to multi-index.

    idx qpp::multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

     Multi-index to non-negative integer index.
```

ket qpp::mket (const std::vector< idx > &mask, const std::vector< idx > &dims)

Multi-partite qudit ket.

ket qpp::mket (const std::vector< idx > &mask, idx d=2)

Multi-partite qudit ket.

cmat qpp::mprj (const std::vector< idx > &mask, const std::vector< idx > &dims)

Projector onto multi-partite qudit ket.

cmat qpp::mprj (const std::vector< idx > &mask, idx d=2)

Projector onto multi-partite qudit ket.

template<typename InputIterator >

```
std::vector< double > qpp::abssq (InputIterator first, InputIterator last)
```

Computes the absolute values squared of an STL-like range of complex numbers.

• template<typename Container >

```
std::vector< double > qpp::abssq (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)
```

Computes the absolute values squared of an STL-like container.

template<typename Derived >

```
std::vector< double > qpp::abssq (const Eigen::MatrixBase< Derived > &A)
```

Computes the absolute values squared of an Eigen expression.

• template<typename InputIterator >

```
std::iterator_traits< InputIterator >::value_type qpp::sum (InputIterator first, InputIterator last)
```

Element-wise sum of an STL-like range.

template<typename Container >

```
Container::value_type qpp::sum (const Container &c, typename std::enable_if< is_iterable< Container >
::value >::type *=nullptr)
```

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

```
std::iterator_traits< InputIterator >::value_type qpp::prod (InputIterator first, InputIterator last)
```

Element-wise product of an STL-like range.

template<typename Container >

```
Container::value_type qpp::prod (const Container &c, typename std::enable_if< is_iterable< Container >
::value >::type *=nullptr)
```

Element-wise product of the elements of an STL-like container.

• template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > qpp::rho2pure (const Eigen::MatrixBase< Derived > &A)
```

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

• std::vector< idx > qpp::complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

```
std::vector< double > qpp::rho2bloch (const Eigen::MatrixBase< Derived > &A)
```

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat qpp::bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

template<char... Bits>

```
ket qpp::literals::operator"" _ket ()
```

Multi-partite qubit ket user-defined literal.

• template<char... Bits>

```
bra qpp::literals::operator"" _bra ()
```

Multi-partite qubit bra user-defined literal.

• template<char... Bits>

```
cmat qpp::literals::operator"" _prj ()
```

Multi-partite qubit projector user-defined literal.


8.16.1 Detailed Description

Generic quantum computing functions.

8.17 input output.h File Reference

Input/output functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 internal::IOManipEigen qpp::disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
 Eigen expression ostream manipulator.

internal::IOManipEigen qpp::disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

• template<typename InputIterator >

internal::IOManipRange< InputIterator > qpp::disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")

Range ostream manipulator.

• template<typename Container >

internal::IOManipRange< typename Container::const_iterator > qpp::disp (const Container &c, const std ::string &separator, const std::string &start="[", const std::string &end="]", typename std::enable_if< is_← iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

• template<typename PointerType >

internal::IOManipPointer< PointerType > qpp::disp (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")

C-style pointer ostream manipulator.

• template<typename Derived >

void qpp::save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.


8.17.1 Detailed Description

Input/output functions.

8.18 instruments.h File Reference

Measurement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)
 Generalized inner product.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

ullet template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >
 std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase
 Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template < typename Derived >

 $std::tuple < idx, std::vector < double >, std::vector < cmat > > qpp::measure (const Eigen::MatrixBase < Derived > &A, const std::initializer_list < cmat > &Ks, const std::vector < idx > &target, const std::vector < idx > &dims)$

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > qpp::measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > qpp::measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, idx d=2)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.


8.18.1 Detailed Description

Measurement functions.

8.19 internal/classes/iomanip.h File Reference

Input/output manipulators.

This graph shows which files directly or indirectly include this file:



Classes

- class qpp::internal::IOManipRange< InputIterator >
- class qpp::internal::IOManipPointer< PointerType >
- class qpp::internal::IOManipEigen

Namespaces

- qpp
 - Quantum++ main namespace.
- qpp::internal

Internal utility functions, do not use them directly or modify them.


8.19.1 Detailed Description

Input/output manipulators.

8.20 internal/classes/singleton.h File Reference

Singleton pattern via CRTP.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::internal::Singleton< T >

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Namespaces

• qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


8.20.1 Detailed Description

Singleton pattern via CRTP.

8.21 internal/util.h File Reference

Internal utility functions.

This graph shows which files directly or indirectly include this file:



Classes

struct qpp::internal::Display_Impl_

Namespaces

qpp

Quantum++ main namespace.

· qpp::internal

Internal utility functions, do not use them directly or modify them.

Functions

- void qpp::internal::n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx qpp::internal::multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- $\bullet \ \ {\it template}{<} {\it typename Derived} >$

bool qpp::internal::check square mat (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

bool qpp::internal::check_vector (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_rvector (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_cvector (const Eigen::MatrixBase< Derived > &A)

• template<typename T >

bool qpp::internal::check nonzero size (const T &x) noexcept

• template<typename T1 , typename T2 >

bool qpp::internal::check_matching_sizes (const T1 &lhs, const T2 &rhs) noexcept

- bool qpp::internal::check dims (const std::vector < idx > &dims)
- template<typename Derived >

bool qpp::internal::check_dims_match_mat (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_dims_match_cvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_dims_match_rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- bool qpp::internal::check eq dims (const std::vector < idx > &dims, idx dim) noexcept
- bool app::internal::check no duplicates (std::vector< idx > v)
- bool qpp::internal::check_subsys_match_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)
- $\bullet \ \ {\it template}{<} {\it typename Derived} >$

bool qpp::internal::check_qubit_matrix (const Eigen::MatrixBase< Derived > &A) noexcept

• template<typename Derived >

bool qpp::internal::check_qubit_cvector (const Eigen::MatrixBase< Derived > &A) noexcept

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

 $bool\ qpp::internal::check_qubit_rvector\ (const\ Eigen::MatrixBase < Derived > \&A)\ noexcept$

• template<typename Derived >

bool qpp::internal::check_qubit_vector (const Eigen::MatrixBase< Derived > &A) noexcept

- bool qpp::internal::check_perm (const std::vector< idx > &perm)
- template<typename Derived1 , typename Derived2 >

 $dyn_mat < typename Derived1::Scalar > qpp::internal::kron2 (const Eigen::MatrixBase < Derived1 > &A, const Eigen::MatrixBase < Derived2 > &B)$

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::internal::dirsum2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::MatrixBase< Derived2 > &B)

• template<typename T >

void qpp::internal::variadic_vector_emplace (std::vector< T > &)

- template<typename T , typename First , typename... Args>
 - void qpp::internal::variadic_vector_emplace (std::vector< T > &v, First &&first, Args &&... args)
- idx qpp::internal::get_num_subsys (idx D, idx d)
- idx qpp::internal::get_dim_subsys (idx sz, idx N)

8.21.1 Detailed Description

Internal utility functions.

8.22 MATLAB/matlab.h File Reference

Input/output interfacing with MATLAB.

```
#include "mat.h"
#include "mex.h"
```

Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< cplx > ::type
 qpp::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::

Scalar > >::type qpp::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >
 std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.


8.22.1 Detailed Description

Input/output interfacing with MATLAB.

8.23 number_theory.h File Reference

Number theory functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

std::vector< int > qpp::x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double qpp::contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

• bigint qpp::gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint qpp::gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint qpp::lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint qpp::lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > qpp::invperm (const std::vector< idx > &perm)

Inverse permutation.

 $\bullet \ \, \text{std::vector} < \mathsf{idx} > \mathsf{qpp::compperm} \ (\mathsf{const} \ \mathsf{std::vector} < \mathsf{idx} > \& \mathsf{perm}, \ \mathsf{const} \ \mathsf{std::vector} < \mathsf{idx} > \& \mathsf{sigma}) \\$

Compose permutations.

std::vector< bigint > qpp::factors (bigint a)

Prime factor decomposition.

• bigint qpp::modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

• bigint qpp::modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple< bigint, bigint, bigint > qpp::egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint qpp::modinv (bigint a, bigint p)

Modular inverse of a mod p.

• bool qpp::isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

• bigint qpp::randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

- std::vector< std::pair< int, int > > qpp::convergents (const std::vector< int > &cf)
 Convergents.
- std::vector< std::pair< int, int > > qpp::convergents (double x, idx N)
 Convergents.


8.23.1 Detailed Description

Number theory functions.

8.24 operations.h File Reference

Quantum operation functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 const std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 idx d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

• template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std \leftrightarrow ::vector< idx > &target, const std::vector< idx > &dims)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std
::vector< idx > &target, idx d=2)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat qpp::kraus2super (const std::vector< cmat > &Ks)

Superoperator matrix.

cmat qpp::kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector< cmat > qpp::choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat qpp::choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat qpp::super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

dyn_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

template<typename Derived >

 $\label{lem:dyn_mat} $$ dyn_mat< typename\ Derived::Scalar > qpp::ptrace2\ (const\ Eigen::MatrixBase<\ Derived > \&A,\ const\ std $$::vector< idx > \&dims)$$

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Partial transpose.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2)

Partial transpose.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &perm, const std::vector< idx > &dims)

Subsystem permutation.

template<typename Derived >

 $\label{lem:dyn_mat} $$ dyn_mat< typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &perm, idx d=2)$

Subsystem permutation.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::applyQFT (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::applyTFQ (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > qpp::TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

• template<typename Derived >

 $dyn_col_vect< typename Derived::Scalar > qpp::QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)$

Qudit quantum Fourier transform.

8.24.1 Detailed Description

Quantum operation functions.

8.25 qpp.h File Reference

Quantum++ main header file, includes all other necessary headers.

```
#include <algorithm>
#include <cassert>
#include <chrono>
#include <cmath>
#include <complex>
#include <cstdlib>
#include <cstring>
#include <exception>
#include <fstream>
```

```
#include <functional>
#include <initializer_list>
#include <iomanip>
#include <iterator>
#include <limits>
#include <memory>
#include <numeric>
#include <ostream>
#include <random>
#include <sstream>
#include <stdexcept>
#include <string>
#include <tuple>
#include <type_traits>
#include <utility>
#include <vector>
#include <Eigen/Dense>
#include <Eigen/SVD>
#include "types.h"
#include "classes/exception.h"
#include "constants.h"
#include "traits.h"
#include "classes/idisplay.h"
#include "internal/util.h"
#include "internal/classes/iomanip.h"
#include "input_output.h"
#include "internal/classes/singleton.h"
#include "classes/random_devices.h"
#include "random.h"
#include "number_theory.h"
#include "functions.h"
#include "classes/init.h"
#include "classes/codes.h"
#include "classes/gates.h"
#include "classes/states.h"
#include "statistics.h"
#include "operations.h"
#include "entropies.h"
#include "entanglement.h"
#include "classes/timer.h"
#include "instruments.h"
#include "classes/reversible.h"
#include "classes/noise.h"
#include "classes/circuits.h"
```

Namespaces

dbb

Quantum++ main namespace.

Macros

#define QPP_UNUSED_

8.25.1 Detailed Description

Quantum++ main header file, includes all other necessary headers.

8.25.2 Macro Definition Documentation


8.25.2.1 QPP_UNUSED_

#define QPP_UNUSED_

8.26 random.h File Reference

Randomness-related functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

double qpp::rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

bigint qpp::rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx qpp::randidx (idx a=std::numeric_limits < idx >::min(), idx b=std::numeric_limits < idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

template<typename Derived >

Derived qpp::rand (idx rows, idx cols, double a=0, double b=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

template<>

dmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

template<>

cmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived qpp::randn (idx rows, idx cols, double mean=0, double sigma=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

• template<>

dmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

template<>

cmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

• double qpp::randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

cmat qpp::randU (idx D=2)

Generates a random unitary matrix.

cmat qpp::randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > qpp::randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat qpp::randH (idx D=2)

Generates a random Hermitian matrix.

ket qpp::randket (idx D=2)

Generates a random normalized ket (pure state vector)

cmat qpp::randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > qpp::randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > qpp::randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.


8.26.1 Detailed Description

Randomness-related functions.

8.27 statistics.h File Reference

Statistics functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

std::vector< double > qpp::uniform (idx N)

Uniform probability distribution vector.

std::vector< double > qpp::marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > qpp::marginalY (const dmat &probXY)

Marginal distribution.

• template<typename Container >

double qpp::avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_← iterable< Container >::value >::type *=nullptr)

Average.

• template<typename Container >

double qpp::cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Covariance.

• template<typename Container >

 $\label{lem:const} \mbox{double qpp::var (const std::vector< double > \&prob, const Container \&X, typename std::enable_if< is_ & iterable< Container >::value >::type *=nullptr) \\$

Variance.

• template<typename Container >

double qpp::sigma (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_← iterable< Container >::value >::type *=nullptr)

Standard deviation.

• template<typename Container >

 $\label{local-container} \begin{tabular}{ll} double & qpp::cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if < is_iterable < Container >::value >::type *=nullptr) \end{tabular}$

Correlation.

8.28 traits.h File Reference 387


8.27.1 Detailed Description

Statistics functions.

8.28 traits.h File Reference

Type traits.

This graph shows which files directly or indirectly include this file:



Classes

struct qpp::make_void< Ts >

Helper for qpp::to_void<> alias template.

struct qpp::is_iterable < T, typename >

Checks whether T is compatible with an STL-like iterable container.

- struct qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(*(std::declval < T >().end(
- struct qpp::is_matrix_expression< Derived >

Checks whether the type is an Eigen matrix expression.

struct qpp::is_complex< T >

Checks whether the type is a complex type.

struct qpp::is_complex< std::complex< T >>

Checks whether the type is a complex number type, specialization for complex types.

Namespaces

• qpp

Quantum++ main namespace.

Typedefs

```
    template<typename... Ts>
        using qpp::to_void = typename make_void< Ts... >::type
        Alias template that implements the proposal for void_t.
```


8.28.1 Detailed Description

Type traits.

8.29 types.h File Reference

Type aliases.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Typedefs

```
• using qpp::idx = std::size t
```

Non-negative integer index, make sure you use an unsigned type.

- using qpp::bigint = long long int
 - Big integer.
- using qpp::cplx = std::complex < double >

Complex number in double precision.

using qpp::ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector.

• using qpp::bra = Eigen::RowVectorXcd

Complex (double precision) dynamic Eigen row vector.

• using qpp::cmat = Eigen::MatrixXcd

Complex (double precision) dynamic Eigen matrix.

• using qpp::dmat = Eigen::MatrixXd

Real (double precision) dynamic Eigen matrix.

• template<typename Scalar >

Dynamic Eigen matrix over the field specified by Scalar.

• template<typename Scalar >

```
using qpp::dyn_col_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 >
```

Dynamic Eigen column vector over the field specified by Scalar.

 $\bullet \ \ \text{template}{<} \text{typename Scalar} >$

```
using qpp::dyn_row_vect = Eigen::Matrix< Scalar, 1, Eigen::Dynamic >
```

Dynamic Eigen row vector over the field specified by Scalar.

Type aliases.

8.30 /Users/vlad/qpp/README.md File Reference

Index

ALL ALL ADDATE LOSS	
/Users/vlad/qpp/README.md, 389	avg
~Codes	qpp, 36
qpp::Codes, 136	
\sim Dynamic_bitset	b00
qpp::Dynamic_bitset, 158	qpp::States, 328
~Gates	b01
qpp::Gates, 174	qpp::States, 329
~IDisplay	b10
qpp::IDisplay, 190	gpp::States, 329
~IJSON	b11
qpp::IJSON, 192	qpp::States, 329
~Init	begin
	_
qpp::lnit, 195	qpp::QCircuit, 273
\sim NoiseBase	bigint
qpp::NoiseBase, 242	qpp, 26
~QCircuit	Bit_circuit
qpp::QCircuit, 273	qpp::Bit_circuit, 131
\sim QEngine	bloch2rho
qpp::QEngine, 294	qpp, 36
~RandomDevices	bra
qpp::RandomDevices, 316	qpp, <mark>26</mark>
~Singleton	11.17
qpp::internal::Singleton, 320	c_reg_
~States	qpp::QCircuit::MeasureStep, 236
	cCTRL_custom
qpp::States, 326	qpp::QCircuit, 276
~Timer	cCTRL
qpp::Timer, 337	
	qpp::QCircuit, 274, 275
A_	CNOTba
qpp::internal::IOManipEigen, 199	qpp::Gates, 183
absm	CNOT
qpp, <mark>28</mark>	qpp::Bit_circuit, 131
abssq	qpp::Bit_circuit::Gate_count, 170
qpp, 29	qpp::Gates, 183
adjoint	CTRL_custom
qpp, 30	qpp::QCircuit, 278
all	CTRL
qpp::Dynamic_bitset, 158	qpp::Gates, 175
anticomm	qpp::QCircuit, 276–278
	cbegin
qpp, 30	o .
any	qpp::QCircuit, 273
qpp::Dynamic_bitset, 158	cend
apply	qpp::QCircuit, 276
qpp, 31–33	check_cvector
applyCTRL	qpp::internal, 120
qpp, 33, 34	check_dims
applyQFT	qpp::internal, 120
qpp, 35	check_dims_match_cvect
applyTFQ	qpp::internal, 120
app. 35	check dims match mat

qpp::internal, 121	compperm
check_dims_match_rvect	qpp, 38
qpp::internal, 121	compute_probs_
check_eq_dims	qpp::NoiseBase, 242
qpp::internal, 121	compute_state_
check_matching_sizes	qpp::NoiseBase, 242
qpp::internal, 121	concurrence
check_no_duplicates	qpp, 40
qpp::internal, 121	conjugate
check_nonzero_size	qpp, 40
qpp::internal, 121	const_iterator
check_perm	qpp::QCircuit, 271
qpp::internal, 122	constants.h, 363
check_qubit_cvector	contfrac2x
qpp::internal, 122	qpp, 40
check_qubit_matrix	convergents
qpp::internal, 122	qpp, 41
check_qubit_rvector	cor
qpp::internal, 122	qpp, 42
check_qubit_vector	cosm
qpp::internal, 122	qpp, 42
check_rvector	count
qpp::internal, 122	qpp::Dynamic_bitset, 158
check_square_mat	COV
qpp::internal, 123	qpp, 43
check_subsys_match_dims	cplx
qpp::internal, 123	qpp, 27
check_vector	ctrl_
qpp::internal, 123	qpp::QCircuit::GateStep, 187
choi2kraus	CustomException
qpp, 36	qpp::exception::CustomException, 138 cwise
choi2super	
qpp, 37	qpp, 43 CZ
chop	qpp::Gates, 183
qpp, 116	qppGates, 163
chop_	d
qpp::internal::IOManipEigen, 199	qpp::NoiseBase, 245
classes/circuits.h, 353	qpp::QCircuit, 290
classes/codes.h, 354	data
classes/exception.h, 355	qpp::Dynamic_bitset, 158
classes/gates.h, 357	det
classes/idisplay.h, 358	qpp, 44
classes/init.h, 358	difference_type
classes/noise.h, 359	qpp::QCircuit::iterator, 213
classes/random_devices.h, 360	dirsum
classes/reversible.h, 361	qpp, 44–46
classes/states.h, 361	dirsum2
classes/timer.h, 362	qpp::internal, 123
cmat	dirsumpow
qpp, 26	qpp, 46
Codes	disp
qpp::Codes, 136	qpp, 47, 48
codeword	display
qpp::Codes, 136	qpp::Dynamic_bitset, 159
comm	qpp::IDisplay, 190
qpp, 37	qpp::QCircuit, 279
complement	qpp::QCircuit::iterator::value_type_, 348
qpp, 38	qpp::QEngine, 294
• • •	

qpp::Timer, 337	qpp::exception::MatrixNotSquare, 225
qpp::internal::IOManipEigen, 199	qpp::exception::MatrixNotSquareNorCvector, 227
qpp::internal::IOManipPointer, 201	qpp::exception::MatrixNotSquareNorRvector, 229
qpp::internal::IOManipRange, 205	qpp::exception::MatrixNotSquareNorVector, 231
display_impl_	qpp::exception::MatrixNotVector, 233
qpp::internal::Display_Impl_, 152	qpp::exception::NoCodeword, 238
dits_	qpp::exception::NotBipartite, 248
qpp::QEngine, 300	qpp::exception::NotImplemented, 250
dmat	qpp::exception::NotQubitCvector, 252
qpp, 27	qpp::exception::NotQubitMatrix, 254
• •	qpp::exception::NotQubitRvector, 256
dyn_col_vect	
qpp, 27	qpp::exception::NotQubitSubsys, 258
dyn_mat	qpp::exception::NotQubitVector, 260
qpp, 27	qpp::exception::OutOfRange, 262
dyn_row_vect	qpp::exception::PermInvalid, 264
qpp, 27	qpp::exception::PermMismatchDims, 266
Dynamic_bitset	qpp::exception::QuditAlreadyMeasured, 311
qpp::Bit_circuit, 132	qpp::exception::SizeMismatch, 322
qpp::Dynamic bitset, 157	qpp::exception::SubsysMismatchDims, 334
	qpp::exception::TypeMismatch, 341
ee	qpp::exception::UndefinedType, 343
qpp, 116	qpp::exception::Unknown, 345
egcd	qpp::exception::ZeroSize, 351
qpp, 49	* * * * * * * * * * * * * * * * * * * *
eig	execute
qpp, 49	qpp::QEngine, 295
	expandout
elem_	qpp::Gates, 175, 176
qpp::QCircuit::iterator, 217	experimental/experimental.h, 367
end	expm
qpp::QCircuit, 279	qpp, 52
end_	
qpp::Timer, 339	FRED
qpp::internal::IOManipPointer, 202	qpp::Bit circuit, 132
qpp::internal::IOManipRange, 205	qpp::Bit_circuit::Gate_count, 171
entanglement	qpp::Gates, 183
qpp, 50	factors
entanglement.h, 364	
entropies.h, 366	qpp, 53
	Fd
entropy	qpp::Gates, 177
qpp, 51	fill_Ks_
eps	qpp::QuditDepolarizingNoise, 314
qpp, 116	fill_probs_
evals	qpp::QuditDepolarizingNoise, 314
qpp, 51	first_
evects	qpp::internal::IOManipRange, 206
qpp, 52	flip
Exception	qpp::Dynamic_bitset, 159
qpp::exception::DimsInvalid, 141	functions.h, 367
qpp::exception::DimsMismatchCvector, 143	funm
qpp::exception::DimsMismatchMatrix, 145	
qpp::exception::DimsMismatchRvector, 147	qpp, 53
	GHZ
qpp::exception::DimsMismatchVector, 149	
qpp::exception::DimsNotEqual, 151	qpp::States, 329
qpp::exception::Duplicates, 154	gate
qpp::exception::Exception, 169	qpp::QCircuit, 280, 281
qpp::exception::InvalidIterator, 197	gate_
qpp::exception::MatrixMismatchSubsys, 219	qpp::QCircuit::GateStep, 187
qpp::exception::MatrixNotCvector, 221	gate_count
qpp::exception::MatrixNotRvector, 223	qpp::Bit_circuit, 134
H 1 1 1	· · · · · · · · · · · · · · · · · · ·

gate_custom	get_name
qpp::QCircuit, 281	qpp::Gates, 178
gate_fan	qpp::QCircuit, 284
qpp::QCircuit, 281, 282	get_nc
gate_type_	qpp::QCircuit, 285
qpp::QCircuit::GateStep, 187	get_non_measured
GateStep	qpp::QCircuit, 285
qpp::QCircuit::GateStep, 186	get_not_measured
GateType	qpp::QEngine, 297
qpp::QCircuit, 271	get_nq
Gates	qpp::QCircuit, 285
qpp::Gates, 174	get_num_subsys
gates	qpp::internal, 123
qpp::QCircuit, 290	get_prng
	qpp::RandomDevices, 317
gates_ip_	get_probs
qpp::QCircuit::iterator::value_type_, 348	qpp::NoiseBase, 244
gcd	qpp:://disebase, 244 qpp::QEngine, 297
qpp, 54	get psi
gconcurrence	3 -
qpp, 54	qpp::QEngine, 297
generated_	get_ref_psi
qpp::NoiseBase, 245	qpp::QEngine, 298
get	get_relative_pos_
qpp::Dynamic_bitset, 160	qpp::QEngine, 298
get_Ks	get_step_count
qpp::NoiseBase, 243	qpp::QCircuit, 285
get_circuit	get_thread_local_instance
qpp::QEngine, 295	qpp::internal::Singleton, 320
get d	grams
qpp::NoiseBase, 243	qpp, 55, 56
qpp::QCircuit, 283	
get_dim_subsys	Н
qpp::internal, 123	qpp::Gates, 183
get dit	heig
qpp::QEngine, 296	qpp, <mark>56</mark>
get_dits	hevals
	qpp, 57
qpp::QEngine, 296	hevects
get_duration	qpp, 57
qpp::Timer, 338	
get_gate_count	i_
qpp::QCircuit, 283	qpp::NoiseBase, 245
get_gates	IDisplay
qpp::QCircuit, 283	qpp::IDisplay, 189
get_instance	IJSON
qpp::internal::Singleton, 320	qpp::IJSON, 192
get_last_idx	IOManipEigen
qpp::NoiseBase, 243	qpp::internal::IOManipEigen, 199
get_last_K	IOManipPointer
qpp::NoiseBase, 244	qpp::internal::IOManipPointer, 201
get_last_p	IOManipRange
qpp::NoiseBase, 244	qpp::internal::IOManipRange, 204, 205
get_measured	Id
qpp::QCircuit, 283, 284	qpp::Gates, 178
qpp::QEngine, 296, 297	Id2
get_measurement_count	qpp::Gates, 184
qpp::QCircuit, 284	idx
get_measurements	qpp, 28
qpp::QCircuit, 284	idx_infty

qpp, 116	load
index_	qpp, 64
qpp::Dynamic_bitset, 160	qpp::RandomDevices, 317
infty	loadMATLAB
qpp, 116	qpp, 64, 65
Init	logdet
qpp::lnit, 195	qpp, 66
input_output.h, 372	logm
instruments.h, 373	qpp, 66
internal/classes/iomanip.h, 374	lognegativity
internal/classes/singleton.h, 375	qpp, 67
internal/util.h, 376	MATLAB/matlab.h, 378
internal::Singleton< const Codes >	MODMUL
qpp::Codes, 137	qpp::Gates, 178
internal::Singleton < const Gates >	marginalX
qpp::Gates, 183	qpp, 67
internal::Singleton < const Init >	marginalY
qpp::Init, 195	qpp, 69
internal::Singleton < const States >	mats
qpp::States, 328	qpp::QCircuit::MeasureStep, 236
internal::Singleton < RandomDevices >	maxn
qpp::RandomDevices, 318	gpp, 116
inverse	measure
qpp, 57	qpp, 69–74
invperm	measure_seq
qpp, 58	qpp, 74, 75
ip	MeasureStep
qpp, 58, 59	qpp::QCircuit::MeasureStep, 235
ip_	MeasureType
<pre>qpp::QCircuit::iterator::value_type_, 348</pre>	qpp::QCircuit, 272
isprime	measured
qpp, 59	qpp::QCircuit, 290
iterator	measurement_type_
qpp::QCircuit::iterator, 214	qpp::QCircuit::MeasureStep, 236
iterator_category	measurements
qpp::QCircuit::iterator, 213	qpp::QCircuit, 290
tu.	measurements_ip_
jn	qpp::QCircuit::iterator::value_type_, 349
qpp::States, 326	measureV
ket	qpp::QCircuit, 286
	measureZ
qpp, 28 kraus2choi	qpp::QCircuit, 287
	mes
qpp, 59 kraus2super	qpp::States, 326
•	minus
qpp, 60	qpp::States, 327
kron	mket
qpp, 60–62	qpp, 75, 76
kron2	modiny
qpp::internal, 124	qpp, 76
kronpow	modmul
qpp, 62	qpp, 77
Ks_ qpp::NoiseBase, 246	modpow
4pp11013cDa3c, 240	qpp, 77
last	mprj
qpp::internal::IOManipRange, 206	qpp, 78
lcm	msg_
qpp, 63	qpp::exception::Exception, 170
MMM, CO	appoxooptionExooption, 170

multiidx2n	qpp::QCircuit::iterator, 215
qpp, 79	qpp::QCircuit::iterator::value_type_, 348
qpp::internal, 124	qpp::Timer, 338
	qpp::internal::IOManipPointer, 202
n2multiidx	qpp::internal::IOManipRange, 205
qpp, 79	qpp::internal::Singleton, 320
qpp::internal, 124	operator==
N_	qpp::Dynamic_bitset, 162
qpp::Dynamic_bitset, 165	qpp::QCircuit::iterator, 216
qpp::internal::IOManipPointer, 202	operator"" _bra
NOT	qpp::literals, 125
qpp::Bit_circuit, 132	operator"" _i
qpp::Bit_circuit::Gate_count, 171	qpp, <mark>82</mark>
name_	qpp::literals, 125
qpp::QCircuit, 290	operator"" _ket
qpp::QCircuit::GateStep, 187	qpp::literals, 126
qpp::QCircuit::MeasureStep, 236	operator"" _prj
nc_	gpp::literals, 126
qpp::QCircuit, 291	-11-12
negativity	p_
qpp, 80	qpp::internal::IOManipPointer, 202
noise_type	pGHZ
qpp::NoiseBase, 241	qpp::States, 330
NoiseBase	pb00
qpp::NoiseBase, 241	qpp::States, 329
none	pb01
qpp::Dynamic_bitset, 160	qpp::States, 329
norm	pb10
qpp, 81	qpp::States, 330
normalize	pb11
qpp, 81	qpp::States, 330
nq_	pi
qpp::QCircuit, 291	qpp, 117
number_theory.h, 378	plus
	qpp::States, 327
offset	pointer
qpp::Dynamic_bitset, 161	qpp::QCircuit::iterator, 213
omega	powm
qpp, 82	qpp, 82
one	prj
qpp::States, 327	qpp, 83
operations.h, 380	prng_
operator!=	qpp::RandomDevices, 318
qpp::Dynamic_bitset, 161	probs
qpp::QCircuit::iterator, 214	qpp::NoiseBase, 246
operator<<	qpp::QEngine, 300
qpp::IDisplay, 191	prod
qpp::QCircuit, 288, 289	
	qpp, 83, 84
operator*	psi_
qpp::QCircuit::iterator, 215	qpp::QEngine, 300
operator()	ptrace
qpp::NoiseBase, 244, 245	qpp, 84, 85
operator++	ptrace1
qpp::QCircuit::iterator, 215	qpp, 85, 86
operator-	ptrace2
qpp::Dynamic_bitset, 161	qpp, 86, 87
operator=	ptranspose
qpp::IDisplay, 190	qpp, 87, 88
qpp::IJSON, 192, 193	pW

_	
qpp::States, 330	dirsumpow, 46
px0	disp, 47, 48
qpp::States, 330	dmat, 27
px1	dyn_col_vect, 27
qpp::States, 330	dyn_mat, 27
py0	dyn_row_vect, 27
qpp::States, 331	ee, 116
py1	egcd, 49
qpp::States, 331	eig, 49
pz0	entanglement, 50
qpp::States, 331	entropy, 51
pz1	eps, 116
qpp::States, 331	evals, 51
OOleanate	evects, 52
QCircuit 870	expm, 52
qpp::QCircuit, 272	factors, 53
QEngine	funm, 53
qpp::QEngine, 294	gcd, 54
QFT	gconcurrence, 54
qpp, 88	grams, 55, 56
qpp::QCircuit, 287	heig, 56
QPP_UNUSED_	hevals, 57
qpp.h, 384	hevects, 57
qcd_	idx, 28
qpp::QCircuit::iterator, 217	idx, 20
qpp::QEngine, 300	infty, 116
qmutualinfo	inverse, 57
qpp, 89	inverse, 57
qpp, 13	•
absm, 28	ip, 58, 59
abssq, 29	isprime, 59
adjoint, 30	ket, 28
anticomm, 30	kraus2choi, 59
apply, 31–33	kraus2super, 60
applyCTRL, 33, 34	kron, 60–62
applyQFT, 35	kronpow, 62
applyTFQ, 35	lcm, 63
avg, 36	load, 64
bigint, 26	loadMATLAB, 64, 65
bloch2rho, 36	logdet, 66
bra, 26	logm, 66
choi2kraus, 36	lognegativity, 67
choi2super, 37	marginalX, 67
chop, 116	marginalY, 69
cmat, 26	maxn, 116
comm, 37	measure, 69–74
complement, 38	measure_seq, 74, 75
compperm, 38	mket, 75, 76
concurrence, 40	modinv, 76
conjugate, 40	modmul, 77
contfrac2x, 40	modpow, 77
convergents, 41	mprj, 78
cor, 42	multiidx2n, 79
cosm, 42	n2multiidx, 79
cov, 43	negativity, 80
cplx, 27	norm, 81
cwise, 43	normalize, 81
det, 44	omega, 82
dirsum, 44–46	operator"" _i, 82
	• = -

pi, 117	FRED, 132
powm, 82	gate_count, 134
prj, 83	NOT, 132
prod, 83, 84	reset, 132
ptrace, 84, 85	SWAP, 133
ptrace1, 85, 86	TOF, 133
ptrace2, 86, 87	X, 133
ptranspose, 87, 88	qpp::Bit_circuit::Gate_count, 170
QFT, 88	CNOT, 170
qmutualinfo, 89	FRED, 171
rand, 90–92	NOT, 171
randH, 92	SWAP, 171
randidx, 93	TOF, 171
randket, 93	X, 171
randkraus, 93	qpp::Codes, 134
randn, 94, 95	~Codes, 136
randperm, 96	Codes, 136
randprime, 96	codeword, 136
randprob, 97	internal::Singleton< const Codes >, 137
randrho, 97	Type, 135
randU, 97	qpp::Dynamic_bitset, 155
randV, 98	\sim Dynamic_bitset, 158
renyi, 98, 99	all, 158
reshape, 99	any, 1 <mark>58</mark>
rho2bloch, 100	count, 158
rho2pure, 100	data, 158
save, 101	display, 159
saveMATLAB, 101, 102	Dynamic_bitset, 157
schatten, 102	flip, 159
schmidtA, 103	get, 160
schmidtB, 103, 104	index_, 160
schmidtcoeffs, 104, 105	N_, 165
schmidtprobs, 105, 106	none, 160
sigma, 106	offset_, 161
sinm, 107	operator!=, 161
spectralpowm, 107	operator-, 161
sqrtm, 108	operator==, 162
sum, 108, 109	rand, 162, 163
super2choi, 109	reset, 163
svals, 110	set, 163, 164
svd, 110	size, 164
svdU, 110	storage size, 164
svdV, 111	storage_size_, 165
syspermute, 111, 112	storage_type, 157
TFQ, 112	to string, 164
to_void, 28	v_, 165
	value type, 157
trace, 112	—71
transpose, 113	qpp::Gates, 172
tsallis, 113, 114	~Gates, 174
uniform, 114	CNOTba, 183
var, 115	CNOT, 183
x2contfrac, 115	CTRL, 175
qpp.h, 382	CZ, 183
QPP_UNUSED_, 384	expandout, 175, 176
qpp::Bit_circuit, 129	FRED, 183
Bit_circuit, 131	Fd, 177
CNOT, 131	Gates, 174
Dynamic_bitset, 132	get_name, 178

H, 183	begin, 273
ld, 178	cCTRL_custom, 276
ld2, 184	cCTRL, 274, 275
internal::Singleton < const Gates >, 183	CTRL_custom, 278
MODMUL, 178	CTRL, 276-278
Rn, 179	cbegin, 273
RX, 179	cend, 276
RY, 180	const_iterator, 271
RZ, 180	d , 290
S, 184	display, 279
SWAPd, 180	end, 279
SWAP, 184	gate, 280, 281
T, 184	gate custom, 281
TOF, 184	gate_fan, 281, 282
X, 184	GateType, 271
Xd, 182	gates_, 290
Y, 185	gates_, 230 get_d, 283
Z, 185	get_gate_count, 283
Zd, 182	get_gates, 283
qpp::IDisplay, 188	get_measured, 283, 284
~IDisplay, 190	get_measurement_count, 284
display, 190	get_measurements, 284
IDisplay, 189	get_name, 284
operator<<, 191	get_nc, 285
operator=, 190	get_non_measured, 285
qpp::IJSON, 191	get_nq, 285
\sim IJSON, 192	get_step_count, 285
IJSON, 192	MeasureType, 272
operator=, 192, 193	measured_, 290
to_JSON, 193	measurements_, 290
qpp::lnit, 193	measureV, 286
∼Init, 195	measureZ, 287
Init, 195	name_, 290
internal::Singleton< const Init >, 195	nc_, 291
qpp::NoiseBase	nq_, 291
\sim NoiseBase, 242	operator<<, 288, 289
compute_probs_, 242	QCircuit, 272
compute state , 242	QFT, 287
d_, 245	step_types_, 291
generated_, 245	StepType, 272
get Ks, 243	TFQ, 287
get_d, 243	to_JSON, 288
get_last_idx, 243	qpp::QCircuit::GateStep, 185
get_last_K, 244	ctrl_, 187
get_last_p, 244	gate_, 187
get_probs, 244	gate_type_, 187
i_, 245	GateStep, 186
Ks_, 246	•
	name_, 187
noise_type, 241	target_, 187
NoiseBase, 241	qpp::QCircuit::MeasureStep, 234
operator(), 244, 245	c_reg_, 236
probs_, 246	mats_, 236
qpp::NoiseBase< T >, 239	MeasureStep, 235
qpp::NoiseType, 246	measurement_type_, 236
qpp::NoiseType::StateDependent, 323	name_, 236
qpp::NoiseType::StateIndependent, 323	target_, 236
qpp::QCircuit, 267	qpp::QCircuit::iterator, 212
\sim QCircuit, 273	difference_type, 213

elem217 iterator_214 iterator_214 iterator_214 iterator_214 iterator_214 iterator_214 iterator_215 operator-1, 215 operator-1, 215 operator-2, 215 operator-2, 215 operator-2, 215 operator-2, 215 operator-2, 215 operator-3, 216 opointer, 213 opd. 2, 217 reference, 213 set_begin_216 set_end_216 value_type, 214 qpp:\(\text{Qirith}\) 216 set_end_2, 216 value_type, 214 qpp:\(\text{Qirith}\) 216 set_end_3, 348 gates_ip348 bi348 measurements_ip349 operator-3, 348 type349 value_type_347 value_type_244 dype_349 value_type_347 value_type_dod_349 value_type_349 value_type_349 value_type_349 value_type_349 value_type_340 value_type_340 value_type_341 value_type_345 value_type_347 value_type_god_349 qpp:\(\text{Qirith}\) 229 display, 224 display, 224 display, 229 display, 229 display, 229 get_display, 229 get_fit_226 get_dis_286 get_dis_286 get_fit_286 get_fit_288 get_relative_pos_298 probs_300 Qesect_289 get_fit_280 get_fit_286 get_fit_380 get_fit_380 get_fit_380 get_fit_380 get_fit_380 get_fit_480 get_fit_480 get_fit_580 get_fit_580 get_fit_580 get_fit_680 get_fi		
Iterator_category, 213		
operator+, 214 operator+, 215 operator+, 215 operator+, 215 operator-, 215 operator-, 215 operator-, 216 operator-, 216 operator-, 217 operator-, 218 operator-, 218 operator-, 219 opera		— —·
operator+, 215 operator-+, 215 operator-+, 215 operator, 216 operator, 216 operator, 217 operator, 217 operator, 218 operator, 218 operator, 219 operator, 218 operator, 219 operator, 21	_ • •	
operator++, 215 operator-=, 216 operator-=, 216 pointer, 213 qcd _ 217 reference, 213 set_begin _ 216 set_end _ 216 value_type, 214 qpp::Octroit-tirerator:value_type_, 346 display, 348 gates_ip_ 348 giates_ip_ 348 ip_ 348 gates_ip_ 348 ip_ 348 gates_ip_ 348 ip_ 348 gates_ip_ 348 ip_ 348 display, 349 qoperator-, 348 ip_ 349 value_type_, 347 value_type_ qcd_, 349 qpp::OErigine, 294 display, 296 get_dite, 295 get_ditt, 296 get_ditt, 296 get_ditt, 296 get_not_measured, 297 get_probs_ 297 get_probs_ 297 get_probs_ 297 get_probs_ 297 get_probs_ 298 probs_ 300 psi_ 300 QEngine, 294 qcd_, 300 qpp::OublithPhaseFlipNoise, 304 QublitBitFlipNoise, 303 qpp::OublitPhasePlipNoise, 305 qpp::OublitPhasePlipNoise, 306 qpp::OublitPhasePlipNoise, 307 QublitPhaseDampingNoise, 307 QublitPhaseDampingNoise, 307 QublitPhaseDampingNoise, 308 qpp::OublitPhaseDampingNoise, 308 qpp::OublitPhaseDampingNoise, 308 qpp::OublitPhaseDampingNoise, 308 qpp::OublitPhasePlapNoise, 308 qpp::OublitPhasePlapNoise, 308 qpp::OublitPhaseDampingNoise, 307 QublitPhaseDampingNoise, 307 quilled partial quality and partial qual	•	· -
operator=, 215 operator=, 216 operator=, 216 operator=, 218 operator=, 218 operator=, 219 operator=, 218 operator=, 219 operator=, 219 operator=, 213 set begin_, 216 set begin_, 216 set end_, 227 set end_, 234 set end_, 234	•	
operator==, 216 pointer, 213 qcd_, 217 reference, 213 set_begin_ 216 set_begin_ 216 set_begin_ 216 set_begin_ 216 set_begin_ 216 set_end_, 216 set_begin_ 216 set_end_, 214 qpp::States, 323 qpp::States, 326 display, 348 gates_ip, 348 gates_ip, 348 measurements_ip_, 349 operator=, 348 measurements_ip_, 349 operator=, 348 value_type_, 347 value_type_, 347 value_type_, 347 value_type_, 349 value_type_qcd_, 349 qpp::States, 328 qpp::Cbrigine, 294 display, 294 display, 294 display, 294 display, 294 display, 294 display, 294 get_dicuit, 295 get_dicuit, 295 get_dit, 296 get_dits_296 get_measured_ 296, 297 get_not_measured_ 296, 297 get_not_measured_ 296, 297 get_not_measured_ 297 pet_not_pass_yand get_relative_pos_, 298 probs_, 300 ceseute_pass_yand probs_, 300 ceseute_pass_yand psi_, 300 ceseute_pass_yand ceseute_p	•	
pointer, 213 qcd_217 reference, 213 set_begin216 set_end216 set_end216 value_lype, 214 qpp::Colircuit:iterator:value_lype 346 display, 348 gates_ip 348 ip 348 gates_ip 348 ip 348 gates_ip 348 ip 349 operator=, 348 type 349 value_lype 347 value_lype 347 value_lype_ 347 qpp::Cefingine, 292	•	
qcd_217 reference, 213 set_begin_, 216 set_end_, 216 set_e	•	•
reference, 213 set_begin_, 216 set_end_, 216 set_end_, 216 value_type, 214 qpp::QCircuit:tirerator:value_type_, 346 display, 348 gates_ip, 348 jb, 348 measurements_ip, 349 operator=, 348 value_type_, 214 qpp::Clarine, 349 value_type_, 347 value_type_, 347 value_type_, 244 display, 300 execute, 295 get_citt, 295 get_citt, 295 get_end_t, 296 get_not_measured, 297 get_probs_297 get_ref_psi, 298 set_dit_298 set_dit_psi, 299 qpp::QubitiPhisseFlipNoise, 301 QubitiPhasePlipNoise, 305 QubitiPhaseDampingNoise, 307 QubitPhaseDampingNoise, 307 QubitPhaseDampingNoise, 308 qpp::QubitPhasePlipNoise, 306 qpp::QubitPhasePlipNoise, 307 QubitPhaseDampingNoise, 308 Timer, 336, 337	·	
set_begin_, 216 rd_,318 set_end_, 216 save, 317 value_type, 214 app::States, 323 app::QCircuit::iterator::value_type_, 346 States, 326 display, 348 b00, 328 gates_ip_, 348 b01, 329 ip_, 348 b10, 329 operator=, 348 GHZ, 329 yalue_type_, 347 jn, 326 value_type_, 347 jn, 326 value_type_ add_, 349 mes, 326 mes, 326 mes, 326 display, 294 one, 327 display, 294 pBOD, 329 display, 294 pBOD, 329 display, 294 pBOD, 329 display, 295 pb10, 330 get_circuit, 295 pb10, 330 get_lit, 296 pb11, 330 get_measured, 295 pb10, 330 get_measured, 296, 297 pX, 330 get_prips, 297 pX, 330 get_psi, 297 pX, 330 get_ref_psi, 298 pX, 331 probs_, 300 p21, 331 psi_, 300 p21, 331		
set_end216 save, 317 value_type, 214 qpp::States, 323 qpp::Colircut::iterator::value_type 346 5tstes, 326 display, 348 b00, 328 gates_ip 348 b01, 329 ip 344 b10, 329 operator=, 348 b11, 329 type 349 internal::Singleton value_type 347 jn, 326 value_type 349 mes, 326 qpp::OEngine, 292 minus, 327 ~CEngine, 294 one, 327 display, 294 pGHZ, 330 execute, 295 pb01, 320 get_oricuit, 295 pb10, 330 get_dit, 296 pb11, 330 get_measured, 296, 297 pw, 330 get_measured, 296, 297 pw, 330 get_probs_ 297 px0, 330 get_pet_is, 298 py1, 331 get_pet_is, 298 py1, 331 get_ref_psi, 298 py1, 331 get_ref_psi, 298 py1, 331 get_dit, 298 py1, 331 get_dit, 298 x1, 332 set_measured_ 299 x1,	•	
value_type, 214 qpp::OCircuit::iterator::value_type_, 346 display, 348 gates_ip 348 jp 349 jp 349 jn 329 measurements_ip 349 operator=, 348 type 347 value_type qod 349 qpp::OEngine, 292 ¬OEngine, 292 ¬OEngine, 294 display, 294 display, 294 display, 294 display, 294 display, 295 get_dircuit, 295 get_dit, 296 get_dit, 296 get_measured, 296, 297 get_probs, 297 get_probs, 297 get_probs_, 298 probs 300 QEngine, 294 qd 300 QEngine, 294 QubitBitFlipNoise, 302 qpp::OubitBitFlipNoise, 302 qpp::OubitBitPhaseFlipNoise, 305 QubitPhaseDampingNoise, 306 Qpp::OubitPhaseDampingNoise, 307 QubitPhaseDampingNoise, 306 Qpp::OubitPhaseDampingNoise, 307 QubitPhaseDampingNoise, 307 QubitPhaseDampingNoise, 306 qpp::OubitPhasePlipNoise, 306 qpp::OubitPhasePlipNoise, 307 QubitPhasePlipNoise, 308 qpp::OubitPhasePlipNoise, 308 qp		
qpp::QCircuit::iterator::value_type_, 346 ~States, 326 display, 348 b00, 328 gates_ip_, 348 b01, 329 ip_ 348 b10, 329 measurements_ip_, 349 b11, 329 operator=, 348 GHZ, 329 type_, 349 internal::Singleton< const States >, 328 value_type_, 347 jn, 326 value_type_, 349 mes, 326 qpp::OEngine, 292 minus, 327 oe. 327 minus, 327 oe. 327 display, 294 display, 294 one, 327 display, 294 pGHZ, 330 get_dit, 295 pb10, 330 get_dit, 296 pb11, 330 get_dit, 296 pb11, 330 get_mot_measured, 297 px0, 330 get_probs, 297 px1, 330 get_relative_pos_, 298 px1, 331 get_relative_pos_, 298 p		
display, 348 gates_ip348 ip348 ip348 ip348 ip348 ip348 ip349 internal:Singleton< const States >, 328 internal:Singleton< const States >, 328 value_type347 value_typeqcd349 internal:Singleton< const States >, 328 internal:Singleton	— · ·	
gates_ip348 ip348 ip349 measurements_ip349 operator=, 348 type349 value_type_347 value_type_qcd349 qpp::\(Cengine, 292\) ~\(Cengine, 294\) display, 294 display, 294 display, 294 display, 294 display, 295 get_circuit, 295 get_circuit, 295 get_dit, 296 get_measured, 297 get_probs_297 get_ref_psi, 298 get_ord, 200 psi300 psi30		
ip 348 measurements_ip 349 operator=, 348 type 349 value_type 347 value_type 349 value_type 349 internal::Singleton< const States >, 328 pyp::OEngine, 292	· ·	
measurements_ip_, 349		
operator=, 348 type 349 type 347 value_type a47 value_type a49 pc)CEngine, 292	• —	
type 349 value_type 347 value_type qcd 349 mes, 326 qpp::QEngine, 292 — QEngine, 294 display, 294 display, 294 dis 300 execute, 295 get_circuit, 295 get_dit, 296 get_dits, 296 get_measured, 297 get_probs, 297 get_ref_psi, 297 get_ref_psi, 298 get_ref_psi, 298 get_ref_psi, 298 get_ref_psi, 298 get_refaility, 298 get_ref_psi, 300 psi 300 psi_	—·—	
value_type 347 jn, 326 value_type_qcd 349 mes, 326 qpp::CEngine, 292 minus, 327 ~CEngine, 294 one, 327 display, 294 p6Hz, 330 display, 294 pb00, 329 display, 295 pb01, 320 gexcute, 295 pb10, 330 get_circuit, 295 pb10, 330 get_dit, 296 plus, 327 get_measured, 296, 297 pW, 330 get_not_measured, 297 px0, 330 get_probs, 297 px1, 330 get_pel_si, 297 py0, 331 get_ref_psi, 298 py1, 331 get_ref_psi, 298 py1, 331 get_relative_pos_, 298 pz0, 331 probs_, 300 pz1, 331 psi_, 300 \$x1, 332 get_relative_pos_, 298 px0, 331 psi_, 300 \$x1, 332 qcd_, 300 \$x32 set_rest, 298 x1, 332 set_dit, 298 x1, 332 set_dit, 298 x1, 332 set_dit, 298 x1, 332 set_dit, 2		
value_type_qcd_, 349 qpp::QEngine, 292 ~QEngine, 294 display, 294 display, 294 display, 294 pGHZ, 330 pb00, 329 execute, 295 get_circuit, 295 get_circuit, 295 get_dit, 296 get_measured, 296, 297 get_not_measured, 297 get_probs, 297 get_pris, 297 get_pris, 298 get_relative_pos_, 298 probs_, 300 QEngine, 294 qcd_, 300 Again, 294 qcd_, 300 reset, 298 set_measured, 299 subsys_, 300 to_JSON, 299 qpp::QubitBitFlipNoise, 302 QubitBitPhaseFlipNoise, 305 QubitPhaseDampingNoise, 307 QubitPhaseDampingNoise, 307 QubitPhaseDampingNoise, 308 qpp::QubitPhasePlipNoise, 308 qpp::QubitPhasePlipNoise, 308 qpp::QubitPhasePlipNoise, 306 QubitChapse PipNoise, 308 qpp::QubitPhasePlipNoise, 307 QubitPhasePlipNoise, 306 Qpp::QubitPhasePlipNoise, 307 QubitPhasePlipNoise, 308 Timer, 336, 337	•• —	_
qpp::QEngine, 292 minus, 327 ~QEngine, 294 one, 327 display, 294 pGHZ, 330 dits_, 300 pb00, 329 execute, 295 pb01, 329 get_circuit, 295 pb10, 330 get_dit, 296 pb11, 330 get_dits, 296 plus, 327 get_measured, 296, 297 pW, 330 get_probs, 297 px1, 330 get_probs, 297 px1, 330 get_ref_psi, 298 py1, 331 get_ref_psi, 298 pz0, 331 get_relative_pos_, 298 pz0, 331 probs_, 300 pz1, 331 psi_, 300 States, 326 QEngine, 294 W, 331 qcd_, 300 x0, 331 reset, 298 x1, 332 set_dit, 298 y1, 332 set_measured_, 299 y1, 332 subsys_, 300 z0, 332 to_JSON, 299 z1, 332 qpp::QubitAmplitudeDampingNoise, 301 zero, 328 QubitBitFlipNoise, 302 ~Timer, 337 QubitBitPhaseFlipNoise, 305 get_duration, 338		-
~QEngine, 294 one, 327 display, 294 pGHZ, 330 dits_, 300 pb00, 329 execute, 295 pb01, 329 get_circuit, 295 pb10, 330 get_dit, 296 pb11, 330 get_measured, 296, 297 pW, 330 get_not_measured, 297 px0, 330 get_probs, 297 px1, 330 get_ref_psi, 297 py0, 331 get_ref_psi, 298 py1, 331 get_ref_psi, 298 pz0, 331 probs_, 300 pz1, 331 psi_, 300 States, 326 QEngine, 294 W, 331 qcd_, 300 x0, 331 reset, 298 x1, 332 set_measured_, 299 x1, 332 set_measured_, 299 y1, 332 subsys_, 300 z0, 332 to_JSON, 299 z1, 332 qpp::QubitAmplitudeDampingNoise, 301 zero, 328 QubitBitPipNoise, 302 qpp::Timer qubitBitPhaseFlipNoise, 305 qpd QubitBitPhaseDampingNoise, 305 operator=, 338 qpp::QubitPhaseDampingNoise, 307		
display, 294 dits_, 300 execute, 295 pet_circuit, 295 pet_circuit, 295 pet_circuit, 296 pet_dit, 296 pet_dits, 296 pet_dits, 296 pet_measured, 296, 297 pet_not_measured, 297 pet_probs, 297 pet_probs, 297 pet_ref_psi, 297 pet_ref_psi, 298 pet_relative_pos_, 298 probs, 300 psi, 300 QEngine, 294 qcd, 300 reset, 298 set_dit, 298 set_dit, 298 set_dit, 298 set_dit, 298 set_dit, 298 set_measured_, 299 put, 331 probs, 300 probs, 300 probs_, 300 probs_, 300 probs_, 300 probs_, 300 qreset, 298 pet_dit, 298 pet_dit, 298 pet_dit, 298 pet_dit, 298 pet_dit, 298 pet_dit, 299 qpp::QubitBifFlipNoise, 301 QubitBifFlipNoise, 302 qpp::QubitBifFlipNoise, 302 qpp::QubitBifFlipNoise, 302 QubitBifFlipNoise, 302 QubitBifFlipNoise, 303 QubitBifPhaseFlipNoise, 305 QubitDepolarizingNoise, 305 QubitPhaseDampingNoise, 307 QubitPhaseDampingNoise, 307 QubitPhaseDampingNoise, 308 qpp::QubitPhaseFlipNoise, 308 qpp::QubitPhaseFlipNoise, 308 qpp::QubitPhaseFlipNoise, 308 Timer, 336, 337		
dits_, 300 pb00, 329 execute, 295 pb01, 329 get_circuit, 295 pb10, 330 get_dit, 296 pb11, 330 get_dits, 296 plus, 327 get_measured, 296, 297 pW, 330 get_probs, 297 px0, 330 get_psi, 297 py0, 331 get_psi, 297 py0, 331 get_ref_psi, 298 p20, 331 get_relative_pos_, 298 p20, 331 probs_, 300 p21, 331 psi_, 300 states, 326 QEngine, 294 W, 331 qcd_, 300 x0, 331 reset, 298 x1, 332 set_dit, 298 y0, 332 set_measured_, 299 y1, 332 subsys_, 300 z0, 332 to_JSON, 299 z1, 332 qpp::QubitAmplitudeDampingNoise, 301 zero, 328 QubitBitFlipNoise, 302 cro, 328 QubitBitPhaseFlipNoise, 304 end_, 339 QubitBitPhaseFlipNoise, 305 get_duration, 338 qpp::QubitPhaseDampingNoise, 305 operator=, 338 QubitPhaseDampingNoise		
execute, 295 get_circuit, 295 get_circuit, 296 get_dit, 296 get_dits, 296 get_dits, 296 get_measured, 296, 297 get_measured, 297 get_not_measured, 297 get_probs, 297 get_probs, 297 get_probs, 297 get_probs, 298 get_relative_pos_, 298 probs_, 300 psi_, 300 QEngine, 294 qcd_, 300 reset, 298 set_dit, 298 set_measured_, 299 subsys_, 300 to_JSON, 299 gp::QubitAmplitudeDampingNoise, 301 QubitBitFlipNoise, 302 QubitBitFlipNoise, 303 QubitBitFlipNoise, 305 QubitBitPhaseFlipNoise, 305 QubitDepolarizingNoise, 306 QubitPhaseDampingNoise, 307 QubitPhaseDampingNoise, 308 Timer, 336, 337		•
get_circuit, 295 get_dit, 296 get_dit, 296 get_dits, 296 get_measured, 296, 297 get_measured, 297 get_probs, 297 get_probs, 297 get_probs, 297 get_probs, 297 get_psi, 297 get_psi, 298 get_relative_pos_, 298 probs_, 300 psi_, 300 psi_, 300 QEngine, 294 QC_ngine, 294 QC_ngine, 298 set_dit, 298 set_dit, 298 set_measured_, 299 subsys_, 300 to_JSON, 299 qpp::QubitAmplitudeDampingNoise, 301 QubitAmplitudeDampingNoise, 302 QubitBitFlipNoise, 303 qpp::QubitBitPhaseFlipNoise, 304 QubitBitPhaseFlipNoise, 305 qpp::QubitBitPhaseFlipNoise, 306 qpp::QubitPhaseDampingNoise, 307 QubitPhaseDampingNoise, 308 Timer, 336, 337		•
get_dit, 296 get_dits, 296 get_dits, 296 get_measured, 296, 297 get_measured, 297 get_not_measured, 297 get_probs, 297 get_probs, 297 get_psi, 297 get_psi, 298 get_ref_psi, 298 get_relative_pos_, 298 probs_, 300 psi_, 300 psi_, 300 QEngine, 294 QCangine, 294 QCangine, 298 set_measured_, 299 subsys_, 300 states, 326 QEngine, 298 set_measured_, 299 subsys_, 300 to_JSON, 299 get_measured_, 299 gpp::QubitBitFlipNoise, 302 QubitBitFlipNoise, 302 QubitBitPhaseFlipNoise, 304 QubitBhaseFlipNoise, 305 QubitPhaseDampingNoise, 307 QubitPhaseDampingNoise, 308 Timer, 336, 337		•
get_dits, 296 plus, 327 get_measured, 296, 297 pW, 330 get_not_measured, 297 px0, 330 get_probs, 297 px1, 330 get_psi, 297 py0, 331 get_ref_psi, 298 py1, 331 get_relative_pos_, 298 pz0, 331 probs_, 300 pz1, 331 psi_, 300 States, 326 QEngine, 294 W, 331 qcd_, 300 x0, 331 reset, 298 x1, 332 set_dit, 298 y0, 332 set_measured_, 299 y1, 332 subsys_, 300 z0, 332 to_JSON, 299 z1, 332 qpp::QubitAmplitudeDampingNoise, 301 zero, 328 QubitBitFlipNoise, 302 qpp::Timer qpp::QubitBitFlipNoise, 303 display, 337 qpp::QubitBitPhaseFlipNoise, 304 end_, 339 QubitBitPhaseFlipNoise, 305 operator=, 338 QubitDepolarizingNoise, 306 start_, 339 qpp::QubitPhaseDampingNoise, 306 start_, 339 qubitDepolarizingNoise, 306 start_, 339 QubitDepolarizingNoise, 308	- -	•
get_measured, 296, 297 get_not_measured, 297 get_probs, 297 get_probs, 297 get_probs, 297 get_probs, 298 get_ref_psi, 298 get_ref_psi, 298 py1, 331 get_refative_pos_, 298 probs_, 300 psi_, 300 psi_, 300 psi_, 300 QEngine, 294 QC_ngine, 294 QC_ngine, 294 QC_ngine, 298 set_dit, 298 set_dit, 298 set_dit, 298 set_measured_, 299 y1, 332 set_dit, 298 set_measured_, 299 y1, 332 subsys_, 300 to_JSON, 299 qpp::QubitAmplitudeDampingNoise, 301 QubitAmplitudeDampingNoise, 301 QubitBitFlipNoise, 302 QubitBitFlipNoise, 303 qpp::QubitBitPhaseFlipNoise, 304 QubitBitPhaseFlipNoise, 305 QubitDepolarizingNoise, 305 QubitDepolarizingNoise, 306 qpp::QubitPhaseDampingNoise, 307 QubitPhaseDampingNoise, 307 QubitPhaseDampingNoise, 308 qpp::QubitPhasePampingNoise, 308 qpp::QubitPhaseDampingNoise, 307 QubitPhaseDampingNoise, 307 QubitPhaseDampingNoise, 308 qpp::QubitPhaseFlipNoise, 308 Timer, 336, 337		
get_not_measured, 297 px0, 330 get_probs, 297 px1, 330 get_psi, 297 py0, 331 get_ref_psi, 298 py1, 331 get_relative_pos_, 298 pz0, 331 probs_, 300 pz1, 331 psi_, 300 States, 326 QEngine, 294 W, 331 qcd_, 300 x0, 331 reset, 298 x1, 332 set_dit, 298 y0, 332 set_measured_, 299 y1, 332 subsys_, 300 z0, 332 to_JSON, 299 z1, 332 qpp::QubitAmplitudeDampingNoise, 301 zero, 328 QubitAmplitudeDampingNoise, 302 qpp::Timer qpp::QubitBitFlipNoise, 303 display, 337 qpp::QubitBitPhaseFlipNoise, 304 end_, 339 QubitBitPhaseFlipNoise, 305 get_duration, 338 qpp::QubitDepolarizingNoise, 306 start_, 339 qpp::QubitPhaseDampingNoise, 307 tic, 338 qubitPhaseFlipNoise, 308 Timer, 336, 337	• —	•
get_probs, 297 px1, 330 get_psi, 297 py0, 331 get_ref_psi, 298 py1, 331 get_relative_pos_, 298 pz0, 331 probs_, 300 pz1, 331 psi_, 300 States, 326 QEngine, 294 W, 331 qcd_, 300 x0, 331 reset, 298 x1, 332 set_dit, 298 y0, 332 set_measured_, 299 y1, 332 subsys_, 300 z0, 332 to_JSON, 299 z1, 332 qpp::QubitAmplitudeDampingNoise, 301 zero, 328 QubitBmplitudeDampingNoise, 302 qpp::Timer qpp::QubitBitFlipNoise, 302 ~Timer, 337 QubitBitPhaseFlipNoise, 304 end_, 339 QubitBitPhaseFlipNoise, 305 get_duration, 338 qpp::QubitDepolarizingNoise, 306 start_, 339 qubitPhaseDampingNoise, 307 tic, 338 QubitPhasePlipNoise, 308 tics, 339 qpp::QubitPhaseFlipNoise, 308 Timer, 336, 337	- -	
get_psi, 297 py0, 331 get_ref_psi, 298 py1, 331 get_relative_pos_, 298 pz0, 331 probs_, 300 pz1, 331 psi_, 300 States, 326 QEngine, 294 W, 331 qcd_, 300 x0, 331 reset, 298 x1, 332 set_dit, 298 y0, 332 set_measured_, 299 y1, 332 subsys_, 300 z0, 332 to_JSON, 299 z1, 332 qpp::QubitAmplitudeDampingNoise, 301 zero, 328 QubitAmplitudeDampingNoise, 302 qpp::Timer qpp::QubitBitFlipNoise, 302 ~Timer, 337 QubitBitFlipNoise, 303 display, 337 qpp::QubitBitPhaseFlipNoise, 304 end_, 339 QubitBitPhaseFlipNoise, 305 get_duration, 338 qpp::QubitDepolarizingNoise, 306 start_, 339 qpp::QubitPhaseDampingNoise, 307 tic, 338 QubitPhaseFlipNoise, 308 tics, 339 qpp::QubitPhaseFlipNoise, 308 Timer, 336, 337		
get_ref_psi, 298 py1, 331 get_relative_pos_, 298 pz0, 331 probs_, 300 pz1, 331 psi_, 300 States, 326 QEngine, 294 W, 331 qcd_, 300 x0, 331 reset, 298 x1, 332 set_dit, 298 y0, 332 set_measured_, 299 y1, 332 subsys_, 300 z0, 332 to_JSON, 299 z1, 332 qpp::QubitAmplitudeDampingNoise, 301 zero, 328 QubitAmplitudeDampingNoise, 302 qpp::Timer qpp::QubitBitFlipNoise, 302 ~Timer, 337 QubitBitFlipNoise, 303 display, 337 qpp::QubitBitPhaseFlipNoise, 304 end_, 339 QubitBitPhaseFlipNoise, 305 get_duration, 338 qpp::QubitDepolarizingNoise, 306 start_, 339 qpp::QubitPhaseDampingNoise, 307 tic, 338 QubitPhaseFlipNoise, 308 tics, 339 qpp::QubitPhaseFlipNoise, 308 Timer, 336, 337	-	
get_relative_pos_, 298		
probs_, 300 psi_, 300 States, 326 QEngine, 294 W, 331 qcd_, 300 x0, 331 reset, 298 x1, 332 set_dit, 298 set_measured_, 299 y1, 332 subsys_, 300 to_JSON, 299 z1, 332 qpp::QubitAmplitudeDampingNoise, 301 QubitAmplitudeDampingNoise, 302 qpp::QubitBitFlipNoise, 302 qpp::QubitBitFlipNoise, 303 qpp::QubitBitFlipNoise, 303 qpp::QubitBitPhaseFlipNoise, 304 QubitBitPhaseFlipNoise, 305 qpp::QubitDepolarizingNoise, 305 QubitDepolarizingNoise, 306 qpp::QubitPhaseDampingNoise, 307 QubitPhaseDampingNoise, 308 qpp::QubitPhaseDampingNoise, 308 qpp::QubitPhaseDampingNoise, 308 qpp::QubitPhaseFlipNoise, 308 qpp::QubitPhaseFlipNoise, 308 Timer, 336, 337		
psi_, 300 States, 326 QEngine, 294 W, 331 qcd_, 300 x0, 331 reset, 298 x1, 332 set_dit, 298 y0, 332 set_measured_, 299 y1, 332 subsys_, 300 z0, 332 to_JSON, 299 z1, 332 qpp::QubitAmplitudeDampingNoise, 301 zero, 328 QubitAmplitudeDampingNoise, 302 qpp::Timer qpp::QubitBitFlipNoise, 302 ~Timer, 337 QubitBitFlipNoise, 303 display, 337 qpp::QubitBitPhaseFlipNoise, 304 end_, 339 QubitBitPhaseFlipNoise, 305 get_duration, 338 qpp::QubitDepolarizingNoise, 305 operator=, 338 QubitDepolarizingNoise, 306 start_, 339 qpp::QubitPhaseDampingNoise, 307 tic, 338 QubitPhaseDampingNoise, 308 tics, 339 qpp::QubitPhaseFlipNoise, 308 Timer, 336, 337		
QEngine, 294 W, 331 qcd_, 300 x0, 331 reset, 298 x1, 332 set_dit, 298 y0, 332 set_measured_, 299 y1, 332 subsys_, 300 z0, 332 to_JSON, 299 z1, 332 qpp::QubitAmplitudeDampingNoise, 301 zero, 328 QubitBitFlipNoise, 302 qpp::Timer qpp::QubitBitFlipNoise, 302 ~Timer, 337 QubitBitFlipNoise, 303 display, 337 qpp::QubitBitPhaseFlipNoise, 304 end_, 339 QubitBitPhaseFlipNoise, 305 get_duration, 338 qpp::QubitDepolarizingNoise, 306 start_, 339 qpp::QubitPhaseDampingNoise, 307 tic, 338 QubitPhaseDampingNoise, 308 tics, 339 qpp::QubitPhaseFlipNoise, 308 Timer, 336, 337		•
qcd_, 300 x0, 331 reset, 298 x1, 332 set_dit, 298 y0, 332 set_measured_, 299 y1, 332 subsys_, 300 z0, 332 to_JSON, 299 z1, 332 qpp::QubitAmplitudeDampingNoise, 301 zero, 328 QubitAmplitudeDampingNoise, 302 qpp::Timer qpp::QubitBitFlipNoise, 302 ~Timer, 337 QubitBitPlipNoise, 303 display, 337 qpp::QubitBitPhaseFlipNoise, 304 end_, 339 QubitBitPhaseFlipNoise, 305 get_duration, 338 qpp::QubitDepolarizingNoise, 305 operator=, 338 QubitDepolarizingNoise, 306 start_, 339 qpp::QubitPhaseDampingNoise, 307 tic, 338 QubitPhaseDampingNoise, 308 tics, 339 qpp::QubitPhaseFlipNoise, 308 Timer, 336, 337		
reset, 298 set_dit, 298 set_dit, 298 set_measured_, 299 y1, 332 subsys, 300 to_JSON, 299 21, 332 qpp::QubitAmplitudeDampingNoise, 301 QubitBitFlipNoise, 302 QubitBitFlipNoise, 303 qpp::QubitBitPhaseFlipNoise, 304 QubitBitPhaseFlipNoise, 305 QubitDepolarizingNoise, 305 qpp::QubitDepolarizingNoise, 306 qpp::QubitPhaseDampingNoise, 307 QubitPhaseDampingNoise, 307 QubitPhaseDampingNoise, 308 Timer, 336, 337		
set_dit, 298 y0, 332 set_measured_, 299 y1, 332 subsys_, 300 z0, 332 to_JSON, 299 z1, 332 qpp::QubitAmplitudeDampingNoise, 301 zero, 328 QubitAmplitudeDampingNoise, 302 qpp::Timer qpp::QubitBitFlipNoise, 302 ~Timer, 337 QubitBitFlipNoise, 303 display, 337 qpp::QubitBitPhaseFlipNoise, 304 end_, 339 QubitBitPhaseFlipNoise, 305 get_duration, 338 qpp::QubitDepolarizingNoise, 305 operator=, 338 QubitDepolarizingNoise, 306 start_, 339 qpp::QubitPhaseDampingNoise, 308 tic, 338 qpp::QubitPhaseFlipNoise, 308 Timer, 336, 337		
set_measured_, 299 subsys_, 300 to_JSON, 299 z1, 332 qpp::QubitAmplitudeDampingNoise, 301 QubitAmplitudeDampingNoise, 302 qpp::QubitBitFlipNoise, 302 QubitBitFlipNoise, 303 qpp::QubitBitPhaseFlipNoise, 304 QubitBitPhaseFlipNoise, 305 QubitBitPhaseFlipNoise, 305 QubitDepolarizingNoise, 305 QubitDepolarizingNoise, 306 qpp::QubitPhaseDampingNoise, 307 QubitPhaseDampingNoise, 308 qpp::QubitPhaseDampingNoise, 308 qpp::QubitPhaseFlipNoise, 308 Timer, 336, 337		
subsys_, 300 to_JSON, 299 z1, 332 qpp::QubitAmplitudeDampingNoise, 301 QubitAmplitudeDampingNoise, 302 qpp::QubitBitFlipNoise, 302 QubitBitFlipNoise, 303 qpp::QubitBitPhaseFlipNoise, 304 QubitBitPhaseFlipNoise, 305 QubitBitPhaseFlipNoise, 305 qpp::QubitDepolarizingNoise, 305 QubitDepolarizingNoise, 306 qpp::QubitPhaseDampingNoise, 307 QubitPhaseDampingNoise, 308 qpp::QubitPhaseFlipNoise, 308 Timer, 336, 337		
to_JSON, 299 z1, 332 qpp::QubitAmplitudeDampingNoise, 301		•
qpp::QubitAmplitudeDampingNoise, 301 QubitAmplitudeDampingNoise, 302 qpp::Timer qpp::QubitBitFlipNoise, 302 QubitBitFlipNoise, 303 qpp::QubitBitPhaseFlipNoise, 304 qpp::QubitBitPhaseFlipNoise, 305 QubitBitPhaseFlipNoise, 305 qpp::QubitDepolarizingNoise, 305 QubitDepolarizingNoise, 306 qpp::QubitPhaseDampingNoise, 307 QubitPhaseDampingNoise, 308 qpp::QubitPhaseFlipNoise, 308 qpp::QubitPhaseFlipNoise, 308 qpp::QubitPhaseFlipNoise, 308 Timer, 336, 337	• —	
QubitAmplitudeDampingNoise, 302 qpp::QubitBitFlipNoise, 302 QubitBitFlipNoise, 303 qpp::QubitBitPhaseFlipNoise, 304 QubitBitPhaseFlipNoise, 305 QubitBitPhaseFlipNoise, 305 qpp::QubitDepolarizingNoise, 305 QubitDepolarizingNoise, 306 qpp::QubitPhaseDampingNoise, 307 QubitPhaseDampingNoise, 308 qpp::QubitPhaseFlipNoise, 308 qpp::QubitPhaseFlipNoise, 308 Timer, 336, 337	-	
qpp::QubitBitFlipNoise, 302~Timer, 337QubitBitFlipNoise, 303display, 337qpp::QubitBitPhaseFlipNoise, 304end_, 339QubitBitPhaseFlipNoise, 305get_duration, 338qpp::QubitDepolarizingNoise, 305operator=, 338QubitDepolarizingNoise, 306start_, 339qpp::QubitPhaseDampingNoise, 307tic, 338QubitPhaseDampingNoise, 308tics, 339qpp::QubitPhaseFlipNoise, 308Timer, 336, 337		
QubitBitFlipNoise, 303 qpp::QubitBitPhaseFlipNoise, 304 qubitBitPhaseFlipNoise, 305 QubitBitPhaseFlipNoise, 305 qpp::QubitDepolarizingNoise, 305 QubitDepolarizingNoise, 306 qpp::QubitPhaseDampingNoise, 307 QubitPhaseDampingNoise, 308 qpp::QubitPhaseFlipNoise, 308 qpp::QubitPhaseFlipNoise, 308 Timer, 336, 337		
qpp::QubitBitPhaseFlipNoise, 304end_, 339QubitBitPhaseFlipNoise, 305get_duration, 338qpp::QubitDepolarizingNoise, 305operator=, 338QubitDepolarizingNoise, 306start_, 339qpp::QubitPhaseDampingNoise, 307tic, 338QubitPhaseDampingNoise, 308tics, 339qpp::QubitPhaseFlipNoise, 308Timer, 336, 337		
QubitBitPhaseFlipNoise, 305 qpp::QubitDepolarizingNoise, 305 QubitDepolarizingNoise, 306 qpp::QubitPhaseDampingNoise, 307 QubitPhaseDampingNoise, 308 qpp::QubitPhaseFlipNoise, 308 qpp::QubitPhaseFlipNoise, 308 qpp::QubitPhaseFlipNoise, 308 Timer, 336, 337	•	· ·
qpp::QubitDepolarizingNoise, 305operator=, 338QubitDepolarizingNoise, 306start_, 339qpp::QubitPhaseDampingNoise, 307tic, 338QubitPhaseDampingNoise, 308tics, 339qpp::QubitPhaseFlipNoise, 308Timer, 336, 337		
QubitDepolarizingNoise, 306 start_, 339 qpp::QubitPhaseDampingNoise, 307 tic, 338 QubitPhaseDampingNoise, 308 tics, 339 qpp::QubitPhaseFlipNoise, 308 Timer, 336, 337	·	- -
qpp::QubitPhaseDampingNoise, 307tic, 338QubitPhaseDampingNoise, 308tics, 339qpp::QubitPhaseFlipNoise, 308Timer, 336, 337		·
QubitPhaseDampingNoise, 308 tics, 339 qpp::QubitPhaseFlipNoise, 308 Timer, 336, 337		
qpp::QubitPhaseFlipNoise, 308 Timer, 336, 337		
	• =	
Quoiti nasei iipinoise, 303 (06, 339		
	שמשונו וומשפו וויףוייטושב, שטש	100, 000

qpp::Timer< T, CLOCK_T >, 335	Exception, 233
qpp::exception, 117	type_description, 234
qpp::exception::CustomException, 137	qpp::exception::NoCodeword, 237
CustomException, 138	Exception, 238
type_description, 139	type_description, 239
what_, 139	qpp::exception::NotBipartite, 247
qpp::exception::DimsInvalid, 140	Exception, 248
Exception, 141	type_description, 248
type_description, 141	qpp::exception::NotImplemented, 249
qpp::exception::DimsMismatchCvector, 142	Exception, 250
Exception, 143	type_description, 250
type_description, 143	qpp::exception::NotQubitCvector, 251
qpp::exception::DimsMismatchMatrix, 144	Exception, 252
Exception, 145	type_description, 252
type_description, 145	qpp::exception::NotQubitMatrix, 253
qpp::exception::DimsMismatchRvector, 146	Exception, 254
Exception, 147	type_description, 254
type_description, 147	qpp::exception::NotQubitRvector, 255
qpp::exception::DimsMismatchVector, 148	Exception, 256
Exception, 149	type_description, 256
type_description, 149	qpp::exception::NotQubitSubsys, 257
qpp::exception::DimsNotEqual, 150	Exception, 258
Exception, 151	type_description, 258
type_description, 151	qpp::exception::NotQubitVector, 259
qpp::exception::Duplicates, 153	Exception, 260
Exception, 154	type_description, 260
type_description, 154	qpp::exception::OutOfRange, 261
qpp::exception::Exception, 166	Exception, 262
Exception, 169	type_description, 262
msg_, 170	qpp::exception::PermInvalid, 263
type_description, 169	Exception, 264
what, 169	type_description, 264
where_, 170	qpp::exception::PermMismatchDims, 265
qpp::exception::InvalidIterator, 195	Exception, 266
Exception, 197	type_description, 266
type_description, 197	qpp::exception::QuditAlreadyMeasured, 310
qpp::exception::MatrixMismatchSubsys, 218	Exception, 311
Exception, 219	type_description, 312
type_description, 220	qpp::exception::SizeMismatch, 321
qpp::exception::MatrixNotCvector, 220	Exception, 322
Exception, 221	type_description, 322
type_description, 222	qpp::exception::SubsysMismatchDims, 333
qpp::exception::MatrixNotRvector, 222	Exception, 334
Exception, 223	type description, 334
type_description, 224	qpp::exception::TypeMismatch, 340
qpp::exception::MatrixNotSquare, 224	Exception, 341
Exception, 225	type_description, 342
type description, 226	qpp::exception::UndefinedType, 342
qpp::exception::MatrixNotSquareNorCvector, 226	Exception, 343
Exception, 227	type_description, 344
type_description, 228	app::exception::Unknown, 344
•• — •	
qpp::exception::MatrixNotSquareNorRvector, 228	Exception, 345
Exception, 229	type_description, 346
type_description, 230	qpp::exception::ZeroSize, 350
qpp::exception::MatrixNotSquareNorVector, 230	Exception, 351
Exception, 231	type_description, 351
type_description, 232	qpp::experimental, 119
qpp::exception::MatrixNotVector, 232	qpp::internal, 119

check_cvector, 120	qpp::internal::Singleton< T >, 318
check_dims, 120	qpp::is_complex< std::complex< T >>, 208
check_dims_match_cvect, 120	qpp::is_complex< T >, 207
check_dims_match_mat, 121	qpp::is_iterable < T, to_void < decltype(std::declval < 7
check dims match rvect, 121	$>$ ().begin()), decltype(std::declval $<$ T $>$ (). \leftarrow
check eq dims, 121	end()), decltype(*(std::declval $<$ T $>$ (). \leftarrow
check_matching_sizes, 121	begin()))>>, 210
check_no_duplicates, 121	qpp::is_iterable< T, typename >, 209
check_nonzero_size, 121	qpp::is_matrix_expression< Derived >, 211
	qpp::literals, 125
check_perm, 122	
check_qubit_cvector, 122	operator"" _bra, 125 operator"" _i, 125
check_qubit_matrix, 122	• —
check_qubit_rvector, 122	operator"" _ket, 126
check_qubit_vector, 122	operator""_prj, 126
check_rvector, 122	qpp::make_void
check_square_mat, 123	type, 218
check_subsys_match_dims, 123	qpp::make_void< Ts >, 217
check_vector, 123	QubitAmplitudeDampingNoise
dirsum2, 123	qpp::QubitAmplitudeDampingNoise, 302
get_dim_subsys, 123	QubitBitFlipNoise
get_num_subsys, 123	qpp::QubitBitFlipNoise, 303
kron2, 124	QubitBitPhaseFlipNoise
multiidx2n, 124	qpp::QubitBitPhaseFlipNoise, 305
n2multiidx, 124	QubitDepolarizingNoise
	qpp::QubitDepolarizingNoise, 306
variadic_vector_emplace, 124	QubitPhaseDampingNoise
qpp::internal::Display_Impl_, 152	qpp::QubitPhaseDampingNoise, 308
display_impl_, 152	QubitPhaseFlipNoise
qpp::internal::IOManipEigen, 197	qpp::QubitPhaseFlipNoise, 309
A_, 199	QuditDepolarizingNoise
chop_, 199	qpp::QuditDepolarizingNoise, 313
display, 199	qppQuditDepolarizing(voise, 515
IOManipEigen, 199	rand
qpp::internal::IOManipPointer	qpp, 90–92
display, 201	qpp::Dynamic_bitset, 162, 163
end_, 202	randH
IOManipPointer, 201	qpp, 92
N_, 202	randidx
operator=, 202	
p_, 202	qpp, 93
separator_, 202	randket
start_, 203	qpp, 93
qpp::internal::IOManipPointer< PointerType >, 200	randkraus
	qpp, 93
qpp::internal::IOManipRange	randn
display, 205	qpp, 94, 95
end_, 205	random.h, 384
first_, 206	RandomDevices
IOManipRange, 204, 205	qpp::RandomDevices, 316
last_, 206	randperm
operator=, 205	qpp, 96
separator_, 206	randprime
start_, 206	qpp, 96
qpp::internal::IOManipRange< InputIterator >, 203	randprob
qpp::internal::Singleton	qpp, 97
\sim Singleton, 320	randrho
get_instance, 320	qpp, 97
get_instance, 320 get_thread_local_instance, 320	randU
operator=, 320	
Singleton, 319, 320	qpp, 97 randV
onigiatori, ora, ozu	randv

qpp, 98	qpp::QCircuit::iterator, 216
rd_	set_measured_
qpp::RandomDevices, 318	qpp::QEngine, 299
reference	sigma
qpp::QCircuit::iterator, 213	qpp, 106
renyi	Singleton
qpp, 98, 99	qpp::internal::Singleton, 319, 320
reset	sinm
qpp::Bit_circuit, 132	qpp, 107
qpp::Dynamic_bitset, 163	size
qpp::QEngine, 298	qpp::Dynamic_bitset, 164
reshape	spectralpowm
qpp, 99	qpp, 107
rho2bloch	sgrtm
qpp, 100	qpp, 108
rho2pure	start
qpp, 100	qpp::Timer, 339
Rn	qpp::internal::IOManipPointer, 203
qpp::Gates, 179	qpp::internal::IOManipRange, 206
RX	States
qpp::Gates, 179	qpp::States, 326
RY	statistics.h, 386
_	
qpp::Gates, 180	step_types_
RZ	qpp::QCircuit, 291
qpp::Gates, 180	StepType
S	qpp::QCircuit, 272
qpp::Gates, 184	storage_size
SWAPd	qpp::Dynamic_bitset, 164
qpp::Gates, 180	storage_size_
SWAP	qpp::Dynamic_bitset, 165
	storage_type
qpp::Bit_circuit, 133	qpp::Dynamic_bitset, 157
qpp::Bit_circuit::Gate_count, 171	subsys_
qpp::Gates, 184	qpp::QEngine, 300
save	sum
qpp, 101	qpp, 108, 109
qpp::RandomDevices, 317	super2choi
saveMATLAB	qpp, 109
qpp, 101, 102	svals
schatten	qpp, 110
qpp, 102	svd
schmidtA	qpp, 110
qpp, 103	svdU
schmidtB	qpp, 110
qpp, 103, 104	svdV
schmidtcoeffs	qpp, 111
qpp, 104, 105	syspermute
schmidtprobs	qpp, 111, 112
qpp, 105, 106	-11-1-7
separator_	Т
qpp::internal::IOManipPointer, 202	qpp::Gates, 184
qpp::internal::IOManipRange, 206	TFQ
set	qpp, 112
qpp::Dynamic_bitset, 163, 164	qpp::QCircuit, 287
set_begin_	TOF
qpp::QCircuit::iterator, 216	qpp::Bit_circuit, 133
set dit	qpp::Bit_circuit::Gate_count, 171
qpp::QEngine, 298	qpp::Gates, 184
set_end_	target_
	9

tics Time	qpp::Timer, 336, 337	٠.	qpp::exception::OutOfRange, 262 qpp::exception::PermInvalid, 264 qpp::exception::PermMismatchDims, 266 qpp::exception::QuditAlreadyMeasured, 312 qpp::exception::SizeMismatch, 322 qpp::exception::SubsysMismatchDims, 334 qpp::exception::TypeMismatch, 342 qpp::exception::UndefinedType, 344 qpp::exception::Unknown, 346 qpp::exception::ZeroSize, 351 s.h, 388
to_s	tring	unifo	
	qpp::Dynamic_bitset, 164		qpp, 114
to_v	oid	.,	
	qpp, 28	v _	annuDunamia hitaat 105
toc			qpp::Dynamic_bitset, 165
	qpp::Timer, 339	valu	e_type
trace			qpp::Dynamic_bitset, 157
liace			qpp::QCircuit::iterator, 214
	qpp, 112	valu	e_type_
	s.h, 387		qpp::QCircuit::iterator::value_type_, 347
trans	spose	valu	e_type_qcd_
	qpp, 113		qpp::QCircuit::iterator::value_type_, 349
tsalli	S	var	
	qpp, 113, 114		qpp, 115
Туре)	varia	adic_vector_emplace
	qpp::Codes, 135	vario	qpp::internal, 124
type	-11-1-		qppinternal, 124
.,,,,	qpp::make_void, 218	W	
typo		**	ann: States 331
type		who	qpp::States, 331
	qpp::QCircuit::iterator::value_type_, 349	wha	
type	_description		qpp::exception::Exception, 169
	qpp::exception::CustomException, 139	wha	_
	qpp::exception::DimsInvalid, 141		qpp::exception::CustomException, 139
	qpp::exception::DimsMismatchCvector, 143	whe	re_
	qpp::exception::DimsMismatchMatrix, 145		qpp::exception::Exception, 170
	qpp::exception::DimsMismatchRvector, 147		
	qpp::exception::DimsMismatchVector, 149	Χ	
	qpp::exception::DimsNotEqual, 151		qpp::Bit_circuit, 133
	qpp::exception::Duplicates, 154		qpp::Bit_circuit::Gate_count, 171
	qpp::exception::Exception, 169		qpp::Gates, 184
	qpp::exception::InvalidIterator, 197	x0	
	qpp::exception::MatrixMismatchSubsys, 220		qpp::States, 331
		x1	
	qpp::exception::MatrixNotCvector, 222		qpp::States, 332
	qpp::exception::MatrixNotRvector, 224	x2cc	ontfrac
	qpp::exception::MatrixNotSquare, 226	X_00	qpp, 115
	qpp::exception::MatrixNotSquareNorCvector, 228	Xd	чрр, 110
	qpp::exception::MatrixNotSquareNorRvector, 230	Λu	annuCatae 100
	qpp::exception::MatrixNotSquareNorVector, 232		qpp::Gates, 182
	qpp::exception::MatrixNotVector, 234	Υ	
	qpp::exception::NoCodeword, 239	ĭ	manuCatas 105
	qpp::exception::NotBipartite, 248	•	qpp::Gates, 185
	qpp::exception::NotImplemented, 250	y0	
			qpp::States, 332
	qpp::exception::NotQubitCvector, 252	y1	
	qpp::exception::NotQubitMatrix, 254		qpp::States, 332
	qpp::exception::NotQubitRvector, 256		
	qpp::exception::NotQubitSubsys, 258	Z	
	qpp::exception::NotQubitVector, 260		qpp::Gates, 185