Quantum++ v1.2

Generated by Doxygen 1.8.14

Contents

1	Qua	ntum++															1
2	Nam	nespace	Index														3
	2.1	Names	space List					 	 	 	 		 	 	 	 	 3
3	Hier	archica	l Index														5
	3.1	Class	Hierarchy					 	 	 	 		 	 	 	 	 5
4	Clas	s Index															7
	4.1	Class	List					 	 	 	 		 	 	 	 	 7
5	File	Index															11
	5.1	File Lis	st					 	 	 	 		 	 	 		 11
6	Nam	nespace	Docume	nta	tion												13
	6.1	qpp Na	amespace	Re	feren	ice .		 	 	 	 		 		 	 	 13
		6.1.1	Detailed	De	scrip	tion		 	 	 	 		 	 	 	 	 26
		6.1.2	Typedef	Dod	cume	entati	on .	 	 	 	 		 	 	 	 	 26
			6.1.2.1	bi	gint			 	 	 	 		 	 	 	 	 26
			6.1.2.2	br	ra .			 	 	 	 		 	 	 	 	 27
			6.1.2.3	cr	mat			 	 	 	 		 	 	 	 	 27
			6.1.2.4	cp	olx .			 	 	 	 		 	 	 		 27
			6.1.2.5	dr	mat			 	 	 	 		 	 	 	 	 27
			6.1.2.6	dy	yn_c	ol_ve	ect .	 	 	 	 		 		 	 	 27
			6.1.2.7	dy	yn_m	nat .		 	 	 	 		 	 	 	 	 28
			6.1.2.8	d١	vn ro	ow v	ect	 	 	 	 		 	 	 	 	 28

ii CONTENTS

	6.1.2.9	idx	28
	6.1.2.10	ket	28
	6.1.2.11	to_void	. 29
6.1.3	Function	Documentation	. 29
	6.1.3.1	absm()	. 29
	6.1.3.2	abssq() [1/3]	. 29
	6.1.3.3	abssq() [2/3]	30
	6.1.3.4	abssq() [3/3]	30
	6.1.3.5	adjoint()	30
	6.1.3.6	anticomm()	31
	6.1.3.7	apply() [1/5]	31
	6.1.3.8	apply() [2/5]	32
	6.1.3.9	apply() [3/5]	32
	6.1.3.10	apply() [4/5]	. 33
	6.1.3.11	apply() [5/5]	. 33
	6.1.3.12	applyCTRL() [1/2]	34
	6.1.3.13	applyCTRL() [2/2]	35
	6.1.3.14	applyQFT()	35
	6.1.3.15	applyTFQ()	. 36
	6.1.3.16	avg()	. 36
	6.1.3.17	bloch2rho()	. 37
	6.1.3.18	choi2kraus()	. 37
	6.1.3.19	choi2super()	. 38
	6.1.3.20	comm()	. 38
	6.1.3.21	complement()	. 39
	6.1.3.22	compperm()	. 39
	6.1.3.23	concurrence()	. 39
	6.1.3.24	conjugate()	40
	6.1.3.25	contfrac2x()	40
	6.1.3.26	convergents() [1/2]	41

6.1.3.27	convergents() [2/2]	41
6.1.3.28	cor()	42
6.1.3.29	cosm()	42
6.1.3.30	cov()	42
6.1.3.31	cwise()	43
6.1.3.32	det()	43
6.1.3.33	dirsum() [1/4]	44
6.1.3.34	dirsum() [2/4]	44
6.1.3.35	dirsum() [3/4]	45
6.1.3.36	dirsum() [4/4]	45
6.1.3.37	dirsumpow()	45
6.1.3.38	disp() [1/5]	46
6.1.3.39	disp() [2/5]	46
6.1.3.40	disp() [3/5]	47
6.1.3.41	disp() [4/5]	47
6.1.3.42	disp() [5/5]	48
6.1.3.43	egcd()	48
6.1.3.44	eig()	49
6.1.3.45	entanglement() [1/2]	49
6.1.3.46	entanglement() [2/2]	50
6.1.3.47	entropy() [1/2]	50
6.1.3.48	entropy() [2/2]	51
6.1.3.49	evals()	51
6.1.3.50	evects()	51
6.1.3.51	expm()	52
6.1.3.52	factors()	52
6.1.3.53	funm()	53
6.1.3.54	gcd() [1/2]	53
6.1.3.55	gcd() [2/2]	54
6.1.3.56	gconcurrence()	54

iv CONTENTS

6.1.3.57	grams() [1/3]	55
6.1.3.58	grams() [2/3]	55
6.1.3.59	grams() [3/3]	55
6.1.3.60	hash_eigen()	56
6.1.3.61	heig()	56
6.1.3.62	hevals()	57
6.1.3.63	hevects()	57
6.1.3.64	inverse()	58
6.1.3.65	invperm()	58
6.1.3.66	ip() [1/2]	58
6.1.3.67	ip() [2/2]	59
6.1.3.68	isprime()	59
6.1.3.69	kraus2choi()	60
6.1.3.70	kraus2super()	60
6.1.3.71	kron() [1/4]	61
6.1.3.72	kron() [2/4]	61
6.1.3.73	kron() [3/4]	62
6.1.3.74	kron() [4/4]	62
6.1.3.75	kronpow()	62
6.1.3.76	lcm() [1/2]	63
6.1.3.77	lcm() [2/2]	63
6.1.3.78	load()	64
6.1.3.79	loadMATLAB() [1/2]	64
6.1.3.80	loadMATLAB() [2/2]	65
6.1.3.81	logdet()	66
6.1.3.82	logm()	66
6.1.3.83	lognegativity() [1/2]	67
6.1.3.84	lognegativity() [2/2]	67
6.1.3.85	marginalX()	67
6.1.3.86	marginalY()	69

6.1.3.87 measure() [1/9]
6.1.3.88 measure() [2/9]
6.1.3.89 measure() [3/9]
6.1.3.90 measure() [4/9]
6.1.3.91 measure() [5/9]
6.1.3.92 measure() [6/9]
6.1.3.93 measure() [7/9]
6.1.3.94 measure() [8/9]
6.1.3.95 measure() [9/9]
6.1.3.96 measure_seq() [1/2]
6.1.3.97 measure_seq() [2/2]
6.1.3.98 mket() [1/2]
6.1.3.99 mket() [2/2]
6.1.3.100 modinv()
6.1.3.101 modmul()
6.1.3.102 modpow()
6.1.3.103 mprj() [1/2]
6.1.3.104 mprj() [2/2]
6.1.3.105 multiidx2n()
6.1.3.106 n2multiidx()
6.1.3.107 negativity() [1/2]
6.1.3.108 negativity() [2/2] 8
6.1.3.109 norm()
6.1.3.110 normalize()
6.1.3.111 omega()
6.1.3.112 operator""""_i()
6.1.3.113 powm()
6.1.3.114 prj()
6.1.3.115 prod() [1/3]
6.1.3.116 prod() [2/3]

vi

6.1.3.117 prod() [3/3]	84
6.1.3.118 ptrace() [1/2]	84
6.1.3.119 ptrace() [2/2]	85
6.1.3.120 ptrace1() [1/2]	85
6.1.3.121 ptrace1() [2/2]	86
6.1.3.122 ptrace2() [1/2]	86
6.1.3.123 ptrace2() [2/2]	87
6.1.3.124 ptranspose() [1/2]	87
6.1.3.125 ptranspose() [2/2]	88
6.1.3.126 QFT()	88
6.1.3.127 qmutualinfo() [1/2]	89
6.1.3.128 qmutualinfo() [2/2]	89
6.1.3.129 rand() [1/5]	90
6.1.3.130 rand() [2/5]	90
6.1.3.131 rand() [3/5]	91
6.1.3.132 rand() [4/5]	91
6.1.3.133 rand() [5/5]	92
6.1.3.134 randH()	92
6.1.3.135 randidx()	93
6.1.3.136 randket()	93
6.1.3.137 randkraus()	93
6.1.3.138 randn() [1/4]	94
6.1.3.139 randn() [2/4]	94
6.1.3.140 randn() [3/4]	95
6.1.3.141 randn() [4/4]	95
6.1.3.142 randperm()	96
6.1.3.143 randprime()	96
6.1.3.144 randprob()	97
6.1.3.145 randrho()	97
6.1.3.146 randU()	97

CONTENTS vii

6.1.3.147 randV()
6.1.3.148 renyi() [1/2]
6.1.3.149 renyi() [2/2]
6.1.3.150 reshape()
6.1.3.151 rho2bloch()
6.1.3.152 rho2pure()
6.1.3.153 save()
6.1.3.154 saveMATLAB() [1/2]
6.1.3.155 saveMATLAB() [2/2]
6.1.3.156 schatten()
6.1.3.157 schmidtA() [1/2]
6.1.3.158 schmidtA() [2/2]
6.1.3.159 schmidtB() [1/2]
6.1.3.160 schmidtB() [2/2]
6.1.3.161 schmidtcoeffs() [1/2]
6.1.3.162 schmidtcoeffs() [2/2]
6.1.3.163 schmidtprobs() [1/2]
6.1.3.164 schmidtprobs() [2/2]
6.1.3.165 sigma()
6.1.3.166 sinm()
6.1.3.167 spectralpowm()
6.1.3.168 sqrtm()
6.1.3.169 sum() [1/3]
6.1.3.170 sum() [2/3]
6.1.3.171 sum() [3/3]
6.1.3.172 super2choi()
6.1.3.173 svals()
6.1.3.174 svd()
6.1.3.175 svdU()
6.1.3.176 svdV()

viii CONTENTS

		6.1.3.177	syspermute() [1/2]	 	 	111
		6.1.3.178	syspermute() [2/2]	 	 	112
		6.1.3.179	TFQ()	 	 	112
		6.1.3.180	trace()	 	 	113
		6.1.3.181	transpose()	 	 	113
		6.1.3.182	tsallis() [1/2]	 	 	113
		6.1.3.183	tsallis() [2/2]	 	 	114
		6.1.3.184	uniform()	 	 	114
		6.1.3.185	var()	 	 	115
		6.1.3.186	x2contfrac()	 	 	115
	6.1.4	Variable	Occumentation	 	 	116
		6.1.4.1	chop	 	 	116
		6.1.4.2	ee	 	 	116
		6.1.4.3	infty	 	 	116
		6.1.4.4	maxn	 	 	116
		6.1.4.5	pi	 	 	116
6.2	qpp::ex	ception N	mespace Reference	 	 	116
	6.2.1	Detailed	Description	 	 	118
6.3	qpp::ex	perimenta	Namespace Reference	 	 	118
	6.3.1	Detailed	Description	 	 	118
6.4	qpp::int	ternal Nan	espace Reference	 	 	118
	6.4.1	Detailed	Description	 	 	120
	6.4.2	Function	Documentation	 	 	120
		6.4.2.1	check_cvector()	 	 	120
		6.4.2.2	check_dims()	 	 	120
		6.4.2.3	check_dims_match_cvect()	 	 	120
		6.4.2.4	check_dims_match_mat()	 	 	120
		6.4.2.5	check_dims_match_rvect()	 	 	121
		6.4.2.6	check_eq_dims()	 	 	121
		6.4.2.7	check_matching_sizes()	 	 	121

		6.4.2.8	check_no_duplicates()	21
		6.4.2.9	check_nonzero_size()	21
		6.4.2.10	check_perm()	21
		6.4.2.11	check_qubit_cvector()	22
		6.4.2.12	check_qubit_matrix()	22
		6.4.2.13	check_qubit_rvector()	22
		6.4.2.14	check_qubit_vector()	22
		6.4.2.15	check_rvector()	22
		6.4.2.16	check_square_mat()	22
		6.4.2.17	check_subsys_match_dims()	23
		6.4.2.18	check_vector()	23
		6.4.2.19	dirsum2()	23
		6.4.2.20	get_dim_subsys()	23
		6.4.2.21	get_num_subsys()	23
		6.4.2.22	hash_combine()	23
		6.4.2.23	kron2()	24
		6.4.2.24	multiidx2n()	24
		6.4.2.25	n2multiidx()	24
		6.4.2.26	variadic_vector_emplace() [1/2]	24
		6.4.2.27	variadic_vector_emplace() [2/2]	24
6.5	qpp::lit	erals Nam	espace Reference	25
	6.5.1	Function	Documentation	25
		6.5.1.1	operator""""_bra()	25
		6.5.1.2	operator""""_i()	25
		6.5.1.3	operator"""" _ket()	26
		6.5.1.4	operator""""_prj()	26

7	Clas	s Docu	mentation	129
	7.1	qpp::B	t_circuit Class Reference	. 129
		7.1.1	Detailed Description	. 131
		7.1.2	Constructor & Destructor Documentation	. 131
			7.1.2.1 Bit_circuit() [1/2]	. 131
			7.1.2.2 Bit_circuit() [2/2]	. 131
			7.1.2.3 ~Bit_circuit()	. 132
		7.1.3	Member Function Documentation	. 132
			7.1.3.1 CNOT()	. 132
			7.1.3.2 FRED()	. 132
			7.1.3.3 get_gate_count()	. 133
			7.1.3.4 get_gate_depth()	. 133
			7.1.3.5 NOT()	. 134
			7.1.3.6 reset()	. 134
			7.1.3.7 SWAP()	. 134
			7.1.3.8 TOF()	. 135
			7.1.3.9 X()	. 135
		7.1.4	Member Data Documentation	. 136
			7.1.4.1 bCNOT	. 136
			7.1.4.2 bFRED	. 136
			7.1.4.3 bNOT	. 136
			7.1.4.4 bSWAP	. 136
			7.1.4.5 bTOF	. 136
			7.1.4.6 btotal	. 136
			7.1.4.7 count	. 137
			7.1.4.8 depth	. 137
	7.2	qpp::C	odes Class Reference	. 137
		7.2.1	Detailed Description	. 138
		7.2.2	Member Enumeration Documentation	. 138
			7.2.2.1 Type	. 138

CONTENTS xi

	7.2.3	Constructor & Destructor Documentation
		7.2.3.1 Codes()
		7.2.3.2 ~Codes()
	7.2.4	Member Function Documentation
		7.2.4.1 codeword()
	7.2.5	Friends And Related Function Documentation
		7.2.5.1 internal::Singleton < const Codes >
7.3	qpp::ex	xception::CustomException Class Reference
	7.3.1	Detailed Description
	7.3.2	Constructor & Destructor Documentation
		7.3.2.1 CustomException()
	7.3.3	Member Function Documentation
		7.3.3.1 description()
	7.3.4	Member Data Documentation
		7.3.4.1 what
7.4	qpp::ex	xception::DimsInvalid Class Reference
	7.4.1	Detailed Description
	7.4.2	Member Function Documentation
		7.4.2.1 description()
		7.4.2.2 Exception()
7.5	qpp::ex	xception::DimsMismatchCvector Class Reference
	7.5.1	Detailed Description
	7.5.2	Member Function Documentation
		7.5.2.1 description()
		7.5.2.2 Exception()
7.6	qpp::ex	cception::DimsMismatchMatrix Class Reference
	7.6.1	Detailed Description
	7.6.2	Member Function Documentation
		7.6.2.1 description()
		7.6.2.2 Exception()

xii CONTENTS

7.7	qpp::ex	cception::DimsMismatchRvector Class Reference	49
	7.7.1	Detailed Description	50
	7.7.2	Member Function Documentation	50
		7.7.2.1 description()	50
		7.7.2.2 Exception()	50
7.8	qpp::ex	cception::DimsMismatchVector Class Reference	51
	7.8.1	Detailed Description	52
	7.8.2	Member Function Documentation	52
		7.8.2.1 description()	52
		7.8.2.2 Exception()	52
7.9	qpp::ex	cception::DimsNotEqual Class Reference	53
	7.9.1	Detailed Description	54
	7.9.2	Member Function Documentation	54
		7.9.2.1 description()	54
		7.9.2.2 Exception()	54
7.10	qpp::in	ternal::Display_Impl_ Struct Reference	55
	7.10.1	Member Function Documentation	55
		7.10.1.1 display_impl_()	55
7.11	qpp::ex	cception::Duplicates Class Reference	56
	7.11.1	Detailed Description	57
	7.11.2	Member Function Documentation	57
		7.11.2.1 description()	57
		7.11.2.2 Exception()	57
7.12	qpp::D	ynamic_bitset Class Reference	57
	7.12.1	Detailed Description	60
	7.12.2	Member Typedef Documentation	60
		7.12.2.1 storage_type	60
		7.12.2.2 value_type	60
	7.12.3	Constructor & Destructor Documentation	60
		7.12.3.1 Dynamic_bitset()	60

CONTENTS xiii

		7.12.3.2 ~Dynamic_bitset()	161
	7.12.4	Member Function Documentation	161
		7.12.4.1 all()	161
		7.12.4.2 any()	161
		7.12.4.3 count()	161
		7.12.4.4 data()	162
		7.12.4.5 display()	162
		7.12.4.6 flip() [1/2]	162
		7.12.4.7 flip() [2/2]	163
		7.12.4.8 get()	163
		7.12.4.9 index_()	163
		7.12.4.10 none()	164
		7.12.4.11 offset_()	164
		7.12.4.12 operator"!=()	164
		7.12.4.13 operator-()	165
		7.12.4.14 operator==()	165
		7.12.4.15 rand() [1/2]	165
		7.12.4.16 rand() [2/2]	166
		7.12.4.17 reset() [1/2]	166
		7.12.4.18 reset() [2/2]	166
		7.12.4.19 set() [1/2]	167
		7.12.4.20 set() [2/2]	167
		7.12.4.21 size()	167
		7.12.4.22 storage_size()	167
		7.12.4.23 to_string()	168
	7.12.5	Member Data Documentation	168
		7.12.5.1 n	168
		7.12.5.2 storage_size	168
		7.12.5.3 v	169
7.13	qpp::int	ernal::EqualEigen Class Reference	169

xiv CONTENTS

	7.13.1	Detailed Description	39
	7.13.2	Member Function Documentation	39
		7.13.2.1 operator()()	39
7.14	qpp::ex	ception::Exception Class Reference	70
	7.14.1	Detailed Description	71
	7.14.2	Constructor & Destructor Documentation	72
		7.14.2.1 Exception()	72
	7.14.3	Member Function Documentation	72
		7.14.3.1 description()	72
		7.14.3.2 what()	73
	7.14.4	Member Data Documentation	73
		7.14.4.1 msg	73
		7.14.4.2 where	73
7.15	qpp::Ga	ates Class Reference	73
	7.15.1	Detailed Description	⁷ 6
	7.15.2	Constructor & Destructor Documentation	⁷ 6
		7.15.2.1 Gates()	⁷ 6
		7.15.2.2 ~Gates()	⁷ 6
	7.15.3	Member Function Documentation	⁷ 6
		7.15.3.1 CTRL()	⁷ 6
		7.15.3.2 expandout() [1/3]	77
		7.15.3.3 expandout() [2/3]	7
		7.15.3.4 expandout() [3/3]	78
		7.15.3.5 Fd()	79
		7.15.3.6 get_name()	79
		7.15.3.7 ld()	30
		7.15.3.8 MODMUL()	30
		7.15.3.9 Rn()	31
		7.15.3.10 RX()	31
		7.15.3.11 RY()	31

CONTENTS xv

		7.15.3.12 RZ()	32
		7.15.3.13 SWAPd()	32
		7.15.3.14 Xd()	32
		7.15.3.15 Zd()	33
	7.15.4	Friends And Related Function Documentation	33
		7.15.4.1 internal::Singleton < const Gates >	33
	7.15.5	Member Data Documentation	33
		7.15.5.1 CNOT	33
		7.15.5.2 CNOTba	34
		7.15.5.3 CZ	34
		7.15.5.4 FRED	34
		7.15.5.5 H	34
		7.15.5.6 ld2	34
		7.15.5.7 S	34
		7.15.5.8 SWAP	35
		7.15.5.9 T	35
		7.15.5.10 TOF	35
		7.15.5.11 X	35
		7.15.5.12 Y	35
		7.15.5.13 Z	35
7.16	qpp::Q0	Circuit::GateStep Struct Reference	36
	7.16.1	Detailed Description	37
	7.16.2	Constructor & Destructor Documentation	37
		7.16.2.1 GateStep() [1/2]	37
		7.16.2.2 GateStep() [2/2]	37
	7.16.3	Member Data Documentation	37
		7.16.3.1 ctrl	37
		7.16.3.2 gate_hash	38
		7.16.3.3 gate_type	38
		7.16.3.4 name	38

xvi CONTENTS

		7.16.3.5 target	188
7.17	qpp::int	ternal::HashEigen Class Reference	188
	7.17.1	Detailed Description	189
	7.17.2	Member Function Documentation	189
		7.17.2.1 operator()()	189
7.18	qpp::ID	Display Class Reference	189
	7.18.1	Detailed Description	190
	7.18.2	Constructor & Destructor Documentation	190
		7.18.2.1 ~IDisplay()	190
	7.18.3	Member Function Documentation	190
		7.18.3.1 display()	190
	7.18.4	Friends And Related Function Documentation	191
		7.18.4.1 operator<<	191
7.19	qpp::IJ	SON Class Reference	191
	7.19.1	Detailed Description	192
	7.19.2	Constructor & Destructor Documentation	192
		7.19.2.1 ~IJSON()	192
	7.19.3	Member Function Documentation	192
		7.19.3.1 to_JSON()	192
7.20	qpp::Ini	it Class Reference	192
	7.20.1	Detailed Description	193
	7.20.2	Constructor & Destructor Documentation	194
		7.20.2.1 Init()	194
		7.20.2.2 ~Init()	194
	7.20.3	Friends And Related Function Documentation	194
		7.20.3.1 internal::Singleton < const Init >	194
7.21	qpp::ex	cception::InvalidIterator Class Reference	194
	7.21.1	Detailed Description	196
	7.21.2	Member Function Documentation	196
		7.21.2.1 description()	196

CONTENTS xvii

		7.21.2.2 Exception()	196
7.22	qpp::int	ternal::IOManipEigen Class Reference	196
	7.22.1	Constructor & Destructor Documentation	198
		7.22.1.1 IOManipEigen() [1/2]	198
		7.22.1.2 IOManipEigen() [2/2]	198
	7.22.2	Member Function Documentation	198
		7.22.2.1 display()	198
	7.22.3	Member Data Documentation	198
		7.22.3.1 A	198
		7.22.3.2 chop	199
7.23	qpp::int	ternal::IOManipPointer< PointerType > Class Template Reference	199
	7.23.1	Constructor & Destructor Documentation	200
		7.23.1.1 IOManipPointer() [1/2]	200
		7.23.1.2 IOManipPointer() [2/2]	200
	7.23.2	Member Function Documentation	200
		7.23.2.1 display()	201
		7.23.2.2 operator=()	201
	7.23.3	Member Data Documentation	201
		7.23.3.1 end	201
		7.23.3.2 N	201
		7.23.3.3 p	201
		7.23.3.4 separator	202
		7.23.3.5 start	202
7.24	qpp::int	ternal::IOManipRange< InputIterator > Class Template Reference	202
	7.24.1	Constructor & Destructor Documentation	203
		7.24.1.1 IOManipRange() [1/2]	204
		7.24.1.2 IOManipRange() [2/2]	204
	7.24.2	Member Function Documentation	204
		7.24.2.1 display()	204
		7.24.2.2 operator=()	204

xviii CONTENTS

	7.24.3	Member Data Documentation
		7.24.3.1 end
		7.24.3.2 first
		7.24.3.3 last
		7.24.3.4 separator
		7.24.3.5 start
7.25	qpp::is_	_complex< T > Struct Template Reference
	7.25.1	Detailed Description
7.26	qpp::is_	_complex< std::complex< T > > Struct Template Reference
	7.26.1	Detailed Description
7.27	qpp::is_	_iterable < T, typename > Struct Template Reference
	7.27.1	Detailed Description
7.28		_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T d()), decltype(*(std::declval < T >().begin())) > Struct Template Reference 20 d())
	7.28.1	Detailed Description
7.29	qpp::is_	_matrix_expression< Derived > Struct Template Reference
	7.29.1	Detailed Description
7.30	qpp::Q0	Circuit::iterator Class Reference
	7.30.1	Detailed Description
	7.30.2	Member Typedef Documentation
		7.30.2.1 difference_type
		7.30.2.2 iterator_category
		7.30.2.3 pointer
		7.30.2.4 reference
		7.30.2.5 value_type
	7.30.3	Constructor & Destructor Documentation
		7.30.3.1 iterator() [1/2]
		7.30.3.2 iterator() [2/2]
	7.30.4	Member Function Documentation
		7.30.4.1 operator"!=()
		7.30.4.2 operator*()

CONTENTS xix

		7.30.4.3 operator++() [1/2]
		7.30.4.4 operator++() [2/2]
		7.30.4.5 operator=()
		7.30.4.6 operator==()
		7.30.4.7 set_begin_()
		7.30.4.8 set_end_()
	7.30.5	Member Data Documentation
		7.30.5.1 elem
		7.30.5.2 qc
7.31	qpp::ma	ake_void< Ts > Struct Template Reference
	7.31.1	Detailed Description
	7.31.2	Member Typedef Documentation
		7.31.2.1 type
7.32	qpp::ex	cception::MatrixMismatchSubsys Class Reference
	7.32.1	Detailed Description
	7.32.2	Member Function Documentation
		7.32.2.1 description()
		7.32.2.2 Exception()
7.33	qpp::ex	cception::MatrixNotCvector Class Reference
	7.33.1	Detailed Description
	7.33.2	Member Function Documentation
		7.33.2.1 description()
		7.33.2.2 Exception()
7.34	qpp::ex	cception::MatrixNotRvector Class Reference
	7.34.1	Detailed Description
	7.34.2	Member Function Documentation
		7.34.2.1 description()
		7.34.2.2 Exception()
7.35	qpp::ex	cception::MatrixNotSquare Class Reference
	7.35.1	Detailed Description

	7.35.2	Member Function Documentation	225
		7.35.2.1 description()	225
		7.35.2.2 Exception()	225
7.36	qpp::ex	cception::MatrixNotSquareNorCvector Class Reference	225
	7.36.1	Detailed Description	227
	7.36.2	Member Function Documentation	227
		7.36.2.1 description()	227
		7.36.2.2 Exception()	227
7.37	qpp::ex	cception::MatrixNotSquareNorRvector Class Reference	227
	7.37.1	Detailed Description	229
	7.37.2	Member Function Documentation	229
		7.37.2.1 description()	229
		7.37.2.2 Exception()	229
7.38	qpp::ex	cception::MatrixNotSquareNorVector Class Reference	229
	7.38.1	Detailed Description	231
	7.38.2	Member Function Documentation	231
		7.38.2.1 description()	231
		7.38.2.2 Exception()	231
7.39	qpp::ex	cception::MatrixNotVector Class Reference	231
	7.39.1	Detailed Description	233
	7.39.2	Member Function Documentation	233
		7.39.2.1 description()	233
		7.39.2.2 Exception()	233
7.40	qpp::Q	Circuit::MeasureStep Struct Reference	233
	7.40.1	Detailed Description	234
	7.40.2	Constructor & Destructor Documentation	234
		7.40.2.1 MeasureStep() [1/2]	235
		7.40.2.2 MeasureStep() [2/2]	235
	7.40.3	Member Data Documentation	235
		7.40.3.1 c_reg	235

CONTENTS xxi

		7.40.3.2 mats_hash
		7.40.3.3 measurement_type
		7.40.3.4 name
		7.40.3.5 target
7.41	qpp::ex	cception::NoCodeword Class Reference
	7.41.1	Detailed Description
	7.41.2	Member Function Documentation
		7.41.2.1 description()
		7.41.2.2 Exception()
7.42	qpp::No	piseBase < T > Class Template Reference
	7.42.1	Detailed Description
	7.42.2	Member Typedef Documentation
		7.42.2.1 noise_type
	7.42.3	Constructor & Destructor Documentation
		7.42.3.1 NoiseBase() [1/2]
		7.42.3.2 NoiseBase() [2/2]
		7.42.3.3 ~NoiseBase()
	7.42.4	Member Function Documentation
		7.42.4.1 compute_probs_()
		7.42.4.2 compute_state_()
		7.42.4.3 get_d()
		7.42.4.4 get_Ks()
		7.42.4.5 get_last_idx()
		7.42.4.6 get_last_K()
		7.42.4.7 get_last_p()
		7.42.4.8 get_probs()
		7.42.4.9 operator()() [1/3]
		7.42.4.10 operator()() [2/3]
		7.42.4.11 operator()() [3/3]
	7.42.5	Member Data Documentation

xxii CONTENTS

		7.42.5.1	d				 	 	 	 	 	 . 2	245
		7.42.5.2	generate	d			 	 	 	 	 	 . 2	245
		7.42.5.3	<u>i_</u>				 	 	 	 	 	 . 2	245
		7.42.5.4	Ks				 	 	 	 	 	 . 2	245
		7.42.5.5	probs				 	 	 	 	 	 . 2	246
7.43	qpp::No	oiseType C	lass Refe	rence .			 	 	 	 	 	 . 2	246
	7.43.1	Detailed I	Description	ı			 	 	 	 	 	 . 2	246
7.44	qpp::ex	ception::N	otBipartite	Class I	Referen	ce	 	 	 	 	 	 . 2	246
	7.44.1	Detailed I	Description	ı			 	 	 	 	 	 . 2	248
	7.44.2	Member F	-unction D	ocume	ntation		 	 	 	 	 	 . 2	248
		7.44.2.1	description	on()			 	 	 	 	 	 . 2	248
		7.44.2.2	Exception	າ()			 	 	 	 	 	 . 2	248
7.45	qpp::ex	ception::N	otImpleme	ented Cl	lass Ref	ference	 	 	 	 	 	 . 2	248
	7.45.1	Detailed I	Description	ı			 	 	 	 	 	 . 2	250
	7.45.2	Member F	Function D	ocume:	ntation		 	 	 	 	 	 . 2	250
		7.45.2.1	description	on()			 	 	 	 	 	 . 2	250
		7.45.2.2	Exception	າ()			 	 	 	 	 	 . 2	250
7.46	qpp::ex	ception::N	otQubitCv	ector Cl	lass Ref	ference	 	 	 	 	 	 . 2	250
	7.46.1	Detailed I	Description	ı			 	 	 	 	 	 . 2	252
	7.46.2	Member F	Function D	ocume:	ntation		 	 	 	 	 	 . 2	252
		7.46.2.1	description	on()			 	 	 	 	 	 . 2	252
		7.46.2.2	Exception	າ()			 	 	 	 	 	 . 2	252
7.47	qpp::ex	ception::N	otQubitMa	ıtrix Cla	ss Refe	rence .	 	 	 	 	 	 . 2	252
	7.47.1	Detailed I	Description	ı			 	 	 	 	 	 . 2	254
	7.47.2	Member F	-unction D	ocume	ntation		 	 	 	 	 	 . 2	254
		7.47.2.1	description	on()			 	 	 	 	 	 . 2	254
		7.47.2.2	Exception	າ()			 	 	 	 	 	 . 2	254
7.48	qpp::ex	ception::N	otQubitRv	ector Cl	lass Ref	ference	 	 	 	 	 	 . 2	254
	7.48.1	Detailed I	Description	ı			 	 	 	 	 	 . 2	256
	7.48.2	Member F	Function D	ocume	ntation		 	 	 	 	 	 . 2	256

CONTENTS xxiii

		7.48.2.1 description()	56
		7.48.2.2 Exception()	56
7.49	qpp::ex	ception::NotQubitSubsys Class Reference	56
	7.49.1	Detailed Description	58
	7.49.2	Member Function Documentation	58
		7.49.2.1 description()	58
		7.49.2.2 Exception()	58
7.50	qpp::ex	ception::NotQubitVector Class Reference	58
	7.50.1	Detailed Description	60
	7.50.2	Member Function Documentation	60
		7.50.2.1 description()	60
		7.50.2.2 Exception()	60
7.51	qpp::ex	ception::OutOfRange Class Reference	60
	7.51.1	Detailed Description	62
	7.51.2	Member Function Documentation	62
		7.51.2.1 description()	62
		7.51.2.2 Exception()	62
7.52	qpp::ex	ception::PermInvalid Class Reference	62
	7.52.1	Detailed Description	64
	7.52.2	Member Function Documentation	64
		7.52.2.1 description()	64
		7.52.2.2 Exception()	64
7.53	qpp::ex	ception::PermMismatchDims Class Reference	64
	7.53.1	Detailed Description	66
	7.53.2	Member Function Documentation	66
		7.53.2.1 description()	66
		7.53.2.2 Exception()	66
7.54	qpp::Q	Circuit Class Reference	67
	7.54.1	Detailed Description	71
	7.54.2	Member Typedef Documentation	71

xxiv CONTENTS

	7.54.2.1 const_iterator	71
7.54.3	Member Enumeration Documentation	71
	7.54.3.1 GateType	71
	7.54.3.2 MeasureType	72
	7.54.3.3 StepType	72
7.54.4	Constructor & Destructor Documentation	73
	7.54.4.1 QCircuit()	73
	7.54.4.2 ~QCircuit()	73
7.54.5	Member Function Documentation	73
	7.54.5.1 add_hash_()	74
	7.54.5.2 begin() [1/2]	74
	7.54.5.3 begin() [2/2]	74
	7.54.5.4 cbegin()	74
	7.54.5.5 cCTRL() [1/4]	75
	7.54.5.6 cCTRL() [2/4]	75
	7.54.5.7 cCTRL() [3/4]	75
	7.54.5.8 cCTRL() [4/4]	76
	7.54.5.9 cCTRL_custom()	76
	7.54.5.10 cend()	77
	7.54.5.11 CTRL() [1/4]	77
	7.54.5.12 CTRL() [2/4]	78
	7.54.5.13 CTRL() [3/4]	78
	7.54.5.14 CTRL() [4/4]	79
	7.54.5.15 CTRL_custom()	79
	7.54.5.16 display()	80
	7.54.5.17 end() [1/2]	80
	7.54.5.18 end() [2/2]	80
	7.54.5.19 gate() [1/3]	80
	7.54.5.20 gate() [2/3]	81
	7.54.5.21 gate() [3/3]	81

CONTENTS xxv

7.54.5.22 gate_custom()
7.54.5.23 gate_fan() [1/3]
7.54.5.24 gate_fan() [2/3]
7.54.5.25 gate_fan() [3/3]
7.54.5.26 get_cmat_hash_tbl_()
7.54.5.27 get_d()
7.54.5.28 get_gate_count()
7.54.5.29 get_gate_depth()
7.54.5.30 get_gates_()
7.54.5.31 get_measured() [1/2]
7.54.5.32 get_measured() [2/2]
7.54.5.33 get_measurement_count() [1/2]
7.54.5.34 get_measurement_count() [2/2]
7.54.5.35 get_measurements_()
7.54.5.36 get_name()
7.54.5.37 get_nc()
7.54.5.38 get_non_measured()
7.54.5.39 get_nop_count()
7.54.5.40 get_nq()
7.54.5.41 get_step_count()
7.54.5.42 measureV() [1/2]
7.54.5.43 measureV() [2/2]
7.54.5.44 measureZ()
7.54.5.45 nop()
7.54.5.46 QFT() [1/3]
7.54.5.47 QFT() [2/3]
7.54.5.48 QFT() [3/3]
7.54.5.49 TFQ() [1/3]
7.54.5.50 TFQ() [2/3]
7.54.5.51 TFQ() [3/3]

xxvi CONTENTS

	7.54.5.52 to_JSON()	292
7.54.6	Friends And Related Function Documentation	292
	7.54.6.1 operator<< [1/4]	292
	7.54.6.2 operator<< [2/4]	293
	7.54.6.3 operator<< [3/4]	293
	7.54.6.4 operator<< [4/4]	293
	7.54.6.5 QEngine	294
7.54.7	Member Data Documentation	294
	7.54.7.1 cmat_hash_tbl	294
	7.54.7.2 count	294
	7.54.7.3 d	294
	7.54.7.4 gates	294
	7.54.7.5 measured	295
	7.54.7.6 measurement_count	295
	7.54.7.7 measurements	295
	7.54.7.8 name	295
	7.54.7.9 nc	295
	7.54.7.10 nq	295
	7.54.7.11 step_types	296
7.55 qpp::Q	Engine Class Reference	296
7.55.1	Detailed Description	298
7.55.2	Constructor & Destructor Documentation	298
	7.55.2.1 QEngine() [1/3]	298
	7.55.2.2 QEngine() [2/3]	299
	7.55.2.3 QEngine() [3/3]	299
	7.55.2.4 ~QEngine()	299
7.55.3	Member Function Documentation	299
	7.55.3.1 display()	299
	7.55.3.2 execute() [1/3]	300
	7.55.3.3 execute() [2/3]	300

CONTENTS xxvii

		7.55.3.4	execute	() [3/3]]						 ٠.	 	 ٠.	 	 300
		7.55.3.5	get_circ	uit() .							 	 	 	 	 300
		7.55.3.6	get_dit()								 	 	 	 	 301
		7.55.3.7	get_dits	()							 	 	 	 	 301
		7.55.3.8	get_mea	asured() [1/2]	١					 	 	 	 	 301
		7.55.3.9	get_mea	asured() [2/2]	١					 	 	 	 	 302
		7.55.3.10	get_non	_meası	ured() .						 	 	 	 	 302
		7.55.3.11	get_prol	bs()							 	 	 	 	 302
		7.55.3.12	get_psi()							 	 	 	 	 303
		7.55.3.13	get_rela	tive_po	s_() .						 	 	 	 	 303
		7.55.3.14	operator	r=()							 	 	 	 	 303
		7.55.3.15	reset()								 	 	 	 	 303
		7.55.3.16	set_dit()								 	 	 	 	 304
		7.55.3.17	set_mea	asured_	_()						 	 	 	 	 305
		7.55.3.18	set_psi()							 	 	 	 	 305
		7.55.3.19	to_JSOI	٧()							 	 	 	 	 306
	7.55.4	Member [Data Doc	umenta	ition						 	 	 	 	 306
		7.55.4.1	dits								 	 	 	 	 306
		7.55.4.2	probs_								 	 	 	 	 306
		7.55.4.3	psi								 	 	 	 	 306
		7.55.4.4	qc								 	 	 	 	 307
		7.55.4.5	subsys_								 	 	 	 	 307
7.56	qpp::Ql	NoisyEngir	ne< Nois	eMode	l > Cla	ss Te	empla	te R	efere	nce	 	 	 	 	 307
	7.56.1	Detailed [Description	on							 	 	 	 	 308
	7.56.2	Construct	or & Des	tructor	Docum	entat	tion .				 	 	 	 	 309
		7.56.2.1	QNoisyl	Engine()						 	 	 	 	 309
	7.56.3	Member F	unction	Docume	entatio	n .					 	 	 	 	 309
		7.56.3.1	execute	() [1/4]]						 	 	 	 	 309
		7.56.3.2	execute	() [2/4]]						 	 	 	 	 309
		7.56.3.3	execute	() [3/4]]						 	 	 	 	 310

xxviii CONTENTS

		7.56.3.4 execute() [4/4]	310
		7.56.3.5 get_noise_results()	310
	7.56.4	Member Data Documentation	310
		7.56.4.1 noise	311
		7.56.4.2 noise_results	311
7.57	qpp::Qı	ubitAmplitudeDampingNoise Class Reference	311
	7.57.1	Detailed Description	312
	7.57.2	Constructor & Destructor Documentation	312
		7.57.2.1 QubitAmplitudeDampingNoise()	312
7.58	qpp::Qı	ubitBitFlipNoise Class Reference	313
	7.58.1	Detailed Description	314
	7.58.2	Constructor & Destructor Documentation	314
		7.58.2.1 QubitBitFlipNoise()	314
7.59	qpp::Qı	ubitBitPhaseFlipNoise Class Reference	314
	7.59.1	Detailed Description	315
	7.59.2	Constructor & Destructor Documentation	315
		7.59.2.1 QubitBitPhaseFlipNoise()	315
7.60	qpp::Qı	ubitDepolarizingNoise Class Reference	316
	7.60.1	Detailed Description	317
	7.60.2	Constructor & Destructor Documentation	317
		7.60.2.1 QubitDepolarizingNoise()	317
7.61	qpp::Qı	ubitPhaseDampingNoise Class Reference	317
	7.61.1	Detailed Description	318
	7.61.2	Constructor & Destructor Documentation	318
		7.61.2.1 QubitPhaseDampingNoise()	318
7.62	qpp::Qı	ubitPhaseFlipNoise Class Reference	319
	7.62.1	Detailed Description	320
	7.62.2	Constructor & Destructor Documentation	320
		7.62.2.1 QubitPhaseFlipNoise()	320
7.63	qpp::ex	cception::QuditAlreadyMeasured Class Reference	320

CONTENTS xxix

	7.63.1	Detailed Description	21
	7.63.2	Member Function Documentation	21
		7.63.2.1 description()	22
		7.63.2.2 Exception()	22
7.64	qpp::Qı	uditDepolarizingNoise Class Reference	22
	7.64.1	Detailed Description	23
	7.64.2	Constructor & Destructor Documentation	23
		7.64.2.1 QuditDepolarizingNoise()	23
	7.64.3	Member Function Documentation	24
		7.64.3.1 fill_Ks_()	24
		7.64.3.2 fill_probs_()	24
7.65	qpp::Ra	andomDevices Class Reference	25
	7.65.1	Detailed Description	26
	7.65.2	Constructor & Destructor Documentation	26
		7.65.2.1 RandomDevices()	26
		7.65.2.2 ~RandomDevices()	27
	7.65.3	Member Function Documentation	27
		7.65.3.1 get_prng()	27
		7.65.3.2 load()	27
		7.65.3.3 save()	27
	7.65.4	Friends And Related Function Documentation	28
		7.65.4.1 internal::Singleton< RandomDevices >	28
	7.65.5	Member Data Documentation	28
		7.65.5.1 prng	28
		7.65.5.2 rd	28
7.66	qpp::int	ternal::Singleton< T > Class Template Reference	28
	7.66.1	Detailed Description	29
	7.66.2	Constructor & Destructor Documentation	29
		7.66.2.1 Singleton() [1/2]	30
		7.66.2.2 Singleton() [2/2]	30

		7.66.2.3 ~Singleton()
	7.66.3	Member Function Documentation
		7.66.3.1 get_instance()
		7.66.3.2 get_thread_local_instance()
		7.66.3.3 operator=()
7.67	qpp::ex	cception::SizeMismatch Class Reference
	7.67.1	Detailed Description
	7.67.2	Member Function Documentation
		7.67.2.1 description()
		7.67.2.2 Exception()
7.68	qpp::No	piseType::StateDependent Class Reference
	7.68.1	Detailed Description
7.69	qpp::No	piseType::StateIndependent Class Reference
	7.69.1	Detailed Description
7.70	qpp::St	ates Class Reference
	7.70.1	Detailed Description
	7.70.2	Constructor & Destructor Documentation
		7.70.2.1 States()
		7.70.2.2 ~States()
	7.70.3	Member Function Documentation
		7.70.3.1 jn()
		7.70.3.2 mes()
		7.70.3.3 minus()
		7.70.3.4 one()
		7.70.3.5 plus()
		7.70.3.6 zero()
	7.70.4	Friends And Related Function Documentation
		7.70.4.1 internal::Singleton < const States >
	7.70.5	Member Data Documentation
		7.70.5.1 b00

CONTENTS xxxi

	7.70.5.2 b01	339
	7.70.5.3 b10	339
	7.70.5.4 b11	339
	7.70.5.5 GHZ	339
	7.70.5.6 pb00	339
	7.70.5.7 pb01	340
	7.70.5.8 pb10	340
	7.70.5.9 pb11	340
	7.70.5.10 pGHZ	340
	7.70.5.11 pW	340
	7.70.5.12 px0	340
	7.70.5.13 px1	341
	7.70.5.14 py0	341
	7.70.5.15 py1	341
	7.70.5.16 pz0	341
	7.70.5.17 pz1	341
	7.70.5.18 W	341
	7.70.5.19 x0	342
	7.70.5.20 x1	342
	7.70.5.21 y0	342
	7.70.5.22 y1	342
	7.70.5.23 z0	342
	7.70.5.24 z1	342
7.71 qp	p::exception::SubsysMismatchDims Class Reference	343
7.	1.1 Detailed Description	344
7.	1.2 Member Function Documentation	344
	7.71.2.1 description()	344
	7.71.2.2 Exception()	344
7.72 qp	o::Timer< T, CLOCK_T > Class Template Reference	345
7.	2.1 Detailed Description	346

xxxii CONTENTS

	7.72.2	Constructor & Destructor Documentation	1 6
		7.72.2.1 Timer()	1 6
		7.72.2.2 ~Timer()	16
	7.72.3	Member Function Documentation	17
		7.72.3.1 display()	17
		7.72.3.2 get_duration()	17
		7.72.3.3 tic()	18
		7.72.3.4 tics()	18
		7.72.3.5 toc()	18
	7.72.4	Member Data Documentation	18
		7.72.4.1 end	18
		7.72.4.2 start	19
7.73	qpp::ex	cception::TypeMismatch Class Reference	19
	7.73.1	Detailed Description	50
	7.73.2	Member Function Documentation	50
		7.73.2.1 description()	50
		7.73.2.2 Exception()	51
7.74	qpp::ex	cception::UndefinedType Class Reference	51
	7.74.1	Detailed Description	52
	7.74.2	Member Function Documentation	52
		7.74.2.1 description()	52
		7.74.2.2 Exception()	53
7.75	qpp::ex	cception::Unknown Class Reference	53
	7.75.1	Detailed Description	54
	7.75.2	Member Function Documentation	54
		7.75.2.1 description()	54
		7.75.2.2 Exception()	55
7.76	qpp::Q	Circuit::iterator::value_type_ Class Reference	55
	7.76.1	Detailed Description	56
	7.76.2	Constructor & Destructor Documentation	56

CONTENTS xxxiii

			7.76.2.1 value_type_() [1/2]	356
			7.76.2.2 value_type_() [2/2]	357
		7.76.3	Member Function Documentation	357
			7.76.3.1 display()	357
			7.76.3.2 operator=()	357
		7.76.4	Member Data Documentation	357
			7.76.4.1 gates_ip	358
			7.76.4.2 ip	358
			7.76.4.3 measurements_ip	358
			7.76.4.4 type	358
			7.76.4.5 value_type_qc	358
	7.77	qpp::ex	xception::ZeroSize Class Reference	359
		7.77.1	Detailed Description	360
		7.77.2	Member Function Documentation	360
			7.77.2.1 description()	360
			7.77.2.2 Exception()	360
8	File	Documo	entation	361
8	File 8.1			
8			s/circuits/circuits.h File Reference	361
8		classes	S/circuits/circuits.h File Reference	361
8	8.1	classes	s/circuits/circuits.h File Reference	361 362
8	8.1	classes 8.1.1 classes 8.2.1	S/circuits/circuits.h File Reference Detailed Description S/circuits/engines.h File Reference	361 362 362
8	8.1	classes 8.1.1 classes 8.2.1	S/circuits/circuits.h File Reference Detailed Description S/circuits/engines.h File Reference Detailed Description	361 362 362 362
8	8.1	classes 8.1.1 classes 8.2.1 classes 8.3.1	S/circuits/circuits.h File Reference Detailed Description S/circuits/engines.h File Reference Detailed Description S/codes.h File Reference Detailed Description	361 362 362 362 363
8	8.1 8.2 8.3	classes 8.1.1 classes 8.2.1 classes 8.3.1	S/circuits/circuits.h File Reference Detailed Description S/circuits/engines.h File Reference Detailed Description S/codes.h File Reference Detailed Description S/exception.h File Reference	361 362 362 363 363
8	8.1 8.2 8.3	classes 8.1.1 classes 8.2.1 classes 8.3.1 classes 8.4.1	Detailed Description S/circuits/engines.h File Reference Detailed Description S/codes.h File Reference Detailed Description S/exception.h File Reference Detailed Description	361 362 362 363 363 363
8	8.1 8.2 8.3	classes 8.1.1 classes 8.2.1 classes 8.3.1 classes 8.4.1	Scircuits/circuits.h File Reference Detailed Description Scircuits/engines.h File Reference Detailed Description Scodes.h File Reference Detailed Description Sexception.h File Reference Detailed Description Sexception.h File Reference Detailed Description Sexception.h File Reference	361 362 362 363 363 363 363
8	8.1 8.2 8.3	classes 8.1.1 classes 8.2.1 classes 8.3.1 classes 8.4.1 classes 8.5.1	Scircuits/circuits.h File Reference Detailed Description Scircuits/engines.h File Reference Detailed Description Scodes.h File Reference Detailed Description Sexception.h File Reference Detailed Description Sexception.h File Reference Detailed Description Sexception.h File Reference	361 362 362 363 363 363 365 365
8	8.1 8.2 8.3 8.4	classes 8.1.1 classes 8.2.1 classes 8.3.1 classes 8.4.1 classes 8.5.1	Detailed Description S/circuits/engines.h File Reference Detailed Description S/codes.h File Reference Detailed Description S/exception.h File Reference Detailed Description S/exception.h File Reference Detailed Description Detailed Description Detailed Description Detailed Description	361 362 362 363 363 363 365 365
8	8.1 8.2 8.3 8.4	classes 8.1.1 classes 8.2.1 classes 8.3.1 classes 8.4.1 classes 8.5.1 classes 8.6.1	Detailed Description S/circuits/engines.h File Reference Detailed Description S/codes.h File Reference Detailed Description S/exception.h File Reference Detailed Description S/gates.h File Reference	361 362 362 363 363 363 365 365 366

	8.7.1	Detailed Description			 	 	 	 	 	367
8.8	classes	/noise.h File Reference	e		 	 	 	 	 	368
	8.8.1	Detailed Description			 	 	 	 	 	368
8.9	classes	/random_devices.h File	e Reference		 	 	 	 	 	369
	8.9.1	Detailed Description			 	 	 	 	 	369
8.10	classes	/reversible.h File Refer	ence		 	 	 	 	 	369
	8.10.1	Detailed Description			 	 	 	 	 	370
8.11	classes	states.h File Referenc	e		 	 	 	 	 	370
	8.11.1	Detailed Description			 	 	 	 	 	371
8.12	classes	timer.h File Reference			 	 	 	 	 	371
	8.12.1	Detailed Description			 	 	 	 	 	371
8.13	constan	ts.h File Reference .			 	 	 	 	 	372
	8.13.1	Detailed Description			 	 	 	 	 	373
8.14	entangle	ement.h File Referenc	е		 	 	 	 	 	373
	8.14.1	Detailed Description			 	 	 	 	 	374
8.15	entropie	es.h File Reference .			 	 	 	 	 	374
	8.15.1	Detailed Description			 	 	 	 	 	375
8.16	experim	ental/experimental.h F	File Referenc	e	 	 	 	 	 	376
	8.16.1	Detailed Description			 	 	 	 	 	376
8.17	function	s.h File Reference			 	 	 	 	 	376
	8.17.1	Detailed Description			 	 	 	 	 	381
8.18	input_o	utput.h File Reference			 	 	 	 	 	381
	8.18.1	Detailed Description			 	 	 	 	 	382
8.19	instrum	ents.h File Reference			 	 	 	 	 	382
	8.19.1	Detailed Description			 	 	 	 	 	383
8.20	internal	/classes/iomanip.h File	Reference		 	 	 	 	 	383
	8.20.1	Detailed Description			 	 	 	 	 	384
8.21	internal	/classes/singleton.h Fi	le Reference	·	 	 	 	 	 	384
	8.21.1	Detailed Description			 	 	 	 	 	385
8.22	internal	/util.h File Reference .			 	 	 	 	 	385

CONTENTS XXXV

	8.22.1	Detailed I	Description			 	386						
8.23	MATLA	NB/matlab.h	n File Refer	ence		 	387						
	8.23.1	Detailed I	Description			 	387						
8.24	numbe	r_theory.h	File Referei	nce		 	387						
	8.24.1	Detailed I	Description			 	389						
8.25	operation	ons.h File	Reference			 	389						
	8.25.1	Detailed I	Description			 	391						
8.26	qpp.h F	File Refere	nce			 	391						
	8.26.1	Detailed I	Description			 	393						
	8.26.2	Macro De	finition Doc	umenta	tion .	 	393						
		8.26.2.1	QPP_UNU	JSED		 	393						
8.27	random	n.h File Re	ference .			 	393						
	8.27.1	Detailed I	Description			 	395						
8.28	statistic	s.h File Re	eference .			 	395						
	8.28.1	Detailed I	Description			 	396						
8.29	traits.h	File Refere	ence			 	396						
	8.29.1	Detailed I	Description			 	397						
8.30	types.h	File Refer	ence			 	397						
	8.30.1	Detailed I	Description			 	398						
			•										
Index													399

Chapter 1

Quantum++

Version 1.2 - 10 February 2019

Build status:

Chat (questions/issues)

About

Quantum++ is a modern C++11 general purpose quantum computing library, composed solely of template header files. Quantum++ is written in standard C++11 and has very low external dependencies, using only the Eigen 3 linear algebra header-only template library and, if available, the OpenMP multi-processing library.

Quantum++ is not restricted to qubit systems or specific quantum information processing tasks, being capable of simulating arbitrary quantum processes. The main design factors taken in consideration were the ease of use, high portability, and high performance. The library's simulation capabilities are only restricted by the amount of available physical memory. On a typical machine (Intel i5 8Gb RAM) Quantum++ can successfully simulate the evolution of 25 qubits in a pure state or of 12 qubits in a mixed state reasonably fast.

To report any bugs or ask for additional features/enhancements, please submit an issue with an appropriate label.

If you are interesting in contributing to this project, feel free to contact me. Alternatively, create a custom branch, add your contribution, then finally create a pull request. If I accept the pull request, I will merge your custom branch with the latest development branch. The latter will eventually be merged into a future release version. To contribute, you need to have a solid knowledge of C++ (preferably C++11), including templates and the standard library, a basic knowledge of quantum computing and linear algebra, and working experience with Eigen 3.

For additional Eigen 3 documentation see http://eigen.tuxfamily.org/dox/. For a simple Eigen 3 quick ASCII reference see http://eigen.tuxfamily.org/dox/AsciiQuickReference.txt.

Copyright (c) 2013 - 2019 Vlad Gheorghiu, vgheorgh AT gmail DOT com.

License

Quantum++ is distributed under the MIT license. Please see the LICENSE file for more details.

Installation instructions and further documentation

Please see the installation guide https://github.com/vsoftco/qpp/blob/master/INSTALL.md "`INSTALL.md`" and the comprehensive Wiki for further documentation and detailed examples.

The official API documentation is available in PDF and HTML formats in the doc folder.

2 Quantum++

Chapter 2

Namespace Index

2.1 Namespace List

Here is a list of all namespaces with brief descriptions:

pp	
Quantum++ main namespace	13
p::exception	
Quantum++ exception hierarchy namespace	116
p::experimental	
Experimental/test functions/classes, do not use or modify	118
p::internal	
Internal utility functions, do not use them directly or modify them	118
p::literals	125

4 Namespace Index

Chapter 3

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

qpp::internal::Display_Impl	5
qpp::internal::IOManipEigen	6
qpp::internal::EqualEigen	9
std::exception	Ĭ
qpp::exception::Exception	0
qpp::exception::CustomException	
qpp::exception::DimsInvalid	
qpp::exception::DimsMismatchCvector	
qpp::exception::DimsMismatchMatrix	
qpp::exception::DimsMismatchRvector	
qpp::exception::DimsMismatchVector	
qpp::exception::DimsNotEqual	
qpp::exception::Duplicates	
qpp::exception::InvalidIterator	
qpp::exception::MatrixMismatchSubsys	
qpp::exception::MatrixNotCvector	
qpp::exception::MatrixNotRvector	1
qpp::exception::MatrixNotSquare	23
qpp::exception::MatrixNotSquareNorCvector	:5
qpp::exception::MatrixNotSquareNorRvector	
qpp::exception::MatrixNotSquareNorVector	
qpp::exception::MatrixNotVector	1
qpp::exception::NoCodeword	6
qpp::exception::NotBipartite	6
qpp::exception::NotImplemented	8
qpp::exception::NotQubitCvector	0
qpp::exception::NotQubitMatrix	2
qpp::exception::NotQubitRvector	4
qpp::exception::NotQubitSubsys	6
qpp::exception::NotQubitVector	8
qpp::exception::OutOfRange	0
qpp::exception::PermInvalid	2
qpp::exception::PermMismatchDims	4
qpp::exception::QuditAlreadyMeasured	0
gpp::exception::SizeMismatch	11

6 Hierarchical Index

qpp::exception::SubsysMismatchDims	343
qpp::exception::TypeMismatch	
qpp::exception::UndefinedType	
qpp::exception::Unknown	
qpp::exception::ZeroSize	
false type	
<pre>app::is_complex < T ></pre>	206
<pre>qpp::is_iterable < T, typename ></pre>	
qpp::QCircuit::GateStep	
qpp::internal::HashEigen	
qpp::IDisplay	
qpp::Dynamic_bitset	
qpp::Bit circuit	
qpp::internal::IOManipEigen	
qpp::internal::IOManipPointer< PointerType >	
qpp::internal::IOManipRange< InputIterator >	
qpp::QCircuit	
qpp::QCircuit::iterator::value_type	
qpp::QEngine	
qpp::QNoisyEngine < NoiseModel >	
$qpp::Timer < T, CLOCK_T > \dots$	
qpp::IJSON	191
qpp::QCircuit	267
qpp::QEngine	296
is_base_of	
qpp::is_matrix_expression< Derived >	210
qpp::QCircuit::iterator	
qpp::make_void< Ts >	
qpp::QCircuit::MeasureStep	
qpp::NoiseBase< T >	
qpp::NoiseBase < NoiseType::StateDependent >	
qpp::QubitAmplitudeDampingNoise	
qpp::QubitPhaseDampingNoise	
"" ·	
qpp::NoiseBase < NoiseType::StateIndependent >	
qpp::QubitBitFlipNoise	
qpp::QubitBitPhaseFlipNoise	
qpp::QubitDepolarizingNoise	
qpp::QubitPhaseFlipNoise	
qpp::QuditDepolarizingNoise	
qpp::NoiseType	246
$qpp::internal::Singleton < T > \dots \dots$	328
qpp::internal::Singleton < const Codes >	328
qpp::Codes	137
qpp::internal::Singleton < const Gates >	328
qpp::Gates	
qpp::internal::Singleton < const Init >	
app::Init	
" '	
qpp::internal::Singleton < const States >	
qpp::States	
qpp::internal::Singleton< RandomDevices >	328
qpp::RandomDevices	325
qpp::NoiseType::StateDependent	333
	333
true type	
<pre>app::is_complex < std::complex < T >></pre>	207
app::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval< T	
>().end()), decltype(*(std::declval< T >().begin()))>>	209
V VID	-

Chapter 4

Class Index

4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

qpp::Bit_circuit	
Classical reversible circuit simulator	
qpp::Codes	
Const Singleton class that defines quantum error correcting codes	
qpp::exception::CustomException	
Custom exception	
qpp::exception::DimsInvalid	
Invalid dimension(s) exception	
qpp::exception::DimsMismatchCvector	
Dimension(s) mismatch column vector size exception	
qpp::exception::DimsMismatchMatrix	
Dimension(s) mismatch matrix size exception	
qpp::exception::DimsMismatchRvector	
Dimension(s) mismatch row vector size exception	
qpp::exception::DimsMismatchVector	
Dimension(s) mismatch vector size exception	
qpp::exception::DimsNotEqual	
Dimensions not equal exception	
qpp::internal::Display_Impl	
qpp::exception::Duplicates	
System (e.g. std::vector) has duplicates exception	
qpp::Dynamic_bitset	
Dynamic bitset class, allows the specification of the number of bits at runtime	
qpp::internal::EqualEigen	
Functor for comparing Eigen expressions for equality	
qpp::exception::Exception	
Base class for generating Quantum++ custom exceptions	
qpp::Gates	
Const Singleton class that implements most commonly used gates	
qpp::QCircuit::GateStep	
One step consisting only of gates/operators in the circuit	
qpp::internal::HashEigen	
Functor for hashing Eigen expressions	
qpp::IDisplay	
Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) of)

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const 189

8 Class Index

qpp::IJSON	
Abstract class (interface) that mandates the definition of very basic JSON serialization support app::Init	191
Const Singleton class that performs additional initializations/cleanups	192
pp::exception::InvalidIterator	102
···	194
qpp::internal::IOManipEigen	196
qpp::internal::IOManipPointer< PointerType >	199
qpp::internal::IOManipRange< InputIterator >	
qpp::is_complex< T >	
Checks whether the type is a complex type	206
qpp::is_complex< std::complex< T >>	
Checks whether the type is a complex number type, specialization for complex types	207
qpp::is_iterable< T, typename >	
Checks whether T is compatible with an STL-like iterable container \dots	208
qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(std::d	ecItype(*(std::decIval<
iterable containers	209
qpp::is_matrix_expression< Derived >	
Checks whether the type is an Eigen matrix expression	210
qpp::QCircuit::iterator	
Quantum circuit bound-checking (safe) iterator	211
qpp::make_void< Ts >	
Helper for qpp::to_void<> alias template	216
qpp::exception::MatrixMismatchSubsys	
Matrix mismatch subsystems exception	217
qpp::exception::MatrixNotCvector	
Matrix is not a column vector exception	219
qpp::exception::MatrixNotRvector	
Matrix is not a row vector exception	221
qpp::exception::MatrixNotSquare	
and the state of t	223
qpp::exception::MatrixNotSquareNorCvector	
Matrix is not square nor column vector exception	225
qpp::exception::MatrixNotSquareNorRvector	007
Matrix is not square nor row vector exception	227
qpp::exception::MatrixNotSquareNorVector	000
Matrix is not square nor vector exception	229
qpp::exception::MatrixNotVector	004
Matrix is not a vector exception	231
qpp::QCircuit::MeasureStep One step consisting only of measurements in the circuit	222
pp::exception::NoCodeword	233
Codeword does not exist exception	236
qpp::NoiseBase< T >	200
Base class for all noise models, derive your particular noise model	238
qpp::NoiseType	200
Contains template tags used to specify the noise type	246
qpp::exception::NotBipartite	210
	246
qpp::exception::NotImplemented	2.10
Code not yet implemented	248
qpp::exception::NotQubitCvector	
Column vector is not 2 x 1 exception	250
qpp::exception::NotQubitMatrix	
Matrix is not 2 x 2 exception	252
qpp::exception::NotQubitRvector	
Row vector is not 1 x 2 exception	254

4.1 Class List

qpp::exception::NotQubitSubsys	
	256
qpp::exception::NotQubitVector	
'	258
qpp::exception::OutOfRange	
	260
qpp::exception::PermInvalid	
•	262
qpp::exception::PermMismatchDims	
'	264
qpp::QCircuit	267
	267
qpp::QEngine Quantum circuit engine, executes qpp::QCircuit	296
qpp::QNoisyEngine < NoiseModel >	230
	307
qpp::QubitAmplitudeDampingNoise	00.
	311
qpp::QubitBitFlipNoise	
	313
qpp::QubitBitPhaseFlipNoise	
	314
qpp::QubitDepolarizingNoise	
Qubit depolarizing noise	316
qpp::QubitPhaseDampingNoise	
Qubit phase damping noise, as described in Nielsen and Chuang	317
qpp::QubitPhaseFlipNoise	
	319
qpp::exception::QuditAlreadyMeasured	
	320
qpp::QuditDepolarizingNoise	000
	322
qpp::RandomDevices Singleton class that manages the source of randomness in the library	325
app::internal::Singleton < T >	323
Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously	
	328
qpp::exception::SizeMismatch	0_0
	331
qpp::NoiseType::StateDependent	
	333
qpp::NoiseType::StateIndependent	
Template tag, used whenever the noise is state-independent	333
qpp::States	
Const Singleton class that implements most commonly used states	333
qpp::exception::SubsysMismatchDims	
,	343
qpp::Timer< T, CLOCK_T >	
	345
qpp::exception::TypeMismatch	0.45
71	349
qpp::exception::UndefinedType	051
71 1	351
qpp::exception::Unknown Unknown exception	353
qpp::QCircuit::iterator::value_type_	000
Value type class for qpp::QCircuit::iterator	355
Abe area or deburger agreementation	200

qpp::exception::ZeroSize												
Object has zero size exception	 	 		 								359

Chapter 5

File Index

5.1 File List

Here is a list of all files with brief descriptions:

constants.h	
Constants	72
entanglement.h	
Entanglement functions	73
entropies.h	
Entropy functions	74
functions.h	
Generic quantum computing functions	76
input_output.h	
Input/output functions	81
instruments.h	
Measurement functions	82
number_theory.h	
Number theory functions	87
operations.h	
Quantum operation functions	89
qpp.h	
Quantum++ main header file, includes all other necessary headers	91
random.h	
Randomness-related functions	J
statistics.h	٠.
Statistics functions	95
traits.h	۰,
Type traits	90
types.h Type aliases	o-
classes/codes.h	31
Quantum error correcting codes	61
classes/exception.h	oc
Exceptions	e:
classes/gates.h	٥٠
Quantum gates	e.
classes/idisplay.h	J.
Display interface via the non-virtual interface (NVI) and very basic JSON serialization support	
interface	6F

12 File Index

classes/init.h	
Initialization	. 367
classes/noise.h	
Noise models	. 368
classes/random_devices.h	
Random devices	. 369
classes/reversible.h	
Support for classical reversible circuits	. 369
classes/states.h	
Quantum states	. 370
classes/timer.h	
Timing	. 371
classes/circuits/circuits.h	
Qudit quantum circuits	. 361
classes/circuits/engines.h	
Qudit quantum engines	. 362
experimental/experimental.h	
Experimental/test functions/classes	. 376
internal/util.h	
Internal utility functions	. 385
internal/classes/iomanip.h	
Input/output manipulators	. 383
internal/classes/singleton.h	
Singleton pattern via CRTP	. 384
MATLAB/matlab.h	
Input/output interfacing with MATLAB	. 387

Chapter 6

Namespace Documentation

6.1 qpp Namespace Reference

Quantum++ main namespace.

Namespaces

· exception

Quantum++ exception hierarchy namespace.

· experimental

Experimental/test functions/classes, do not use or modify.

internal

Internal utility functions, do not use them directly or modify them.

literals

Classes

• class Bit_circuit

Classical reversible circuit simulator.

• class Codes

const Singleton class that defines quantum error correcting codes

· class Dynamic_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime.

· class Gates

const Singleton class that implements most commonly used gates

class IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

class IJSON

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

class Init

const Singleton class that performs additional initializations/cleanups

· struct is complex

Checks whether the type is a complex type.

- struct is_complex< std::complex< T > >

Checks whether the type is a complex number type, specialization for complex types.

· struct is_iterable

Checks whether T is compatible with an STL-like iterable container.

 $\bullet \ \ struct\ is_iterable < T,\ to_void < \ decltype(std::declval < T>().begin()),\ decltype(std::declval < T>().end()),\ decltype(*(std::declval < T>().end())),\ decltype(*(std::declval < T>().end()$

Checks whether T is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

• struct is_matrix_expression

Checks whether the type is an Eigen matrix expression.

· struct make void

Helper for qpp::to_void<> alias template.

· class NoiseBase

Base class for all noise models, derive your particular noise model.

class NoiseType

Contains template tags used to specify the noise type.

class QCircuit

Quantum circuit class.

class QEngine

Quantum circuit engine, executes qpp::QCircuit.

class QNoisyEngine

Noisy quantum circuit engine, executes qpp::QCircuit.

· class QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

• class QubitBitFlipNoise

Qubit bit flip noise.

· class QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

· class QubitDepolarizingNoise

Qubit depolarizing noise.

• class QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

· class QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

· class QuditDepolarizingNoise

Qudit depolarizing noise.

· class RandomDevices

Singleton class that manages the source of randomness in the library.

· class States

const Singleton class that implements most commonly used states

class Timer

Chronometer.

Typedefs

```
    template<typename... Ts>
        using to_void = typename make_void< Ts... >::type
```

Alias template that implements the proposal for void_t.

using idx = std::size_t

Non-negative integer index, make sure you use an unsigned type.

• using bigint = long long int

Big integer.

• using cplx = std::complex< double >

Complex number in double precision.

• using ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector.

• using bra = Eigen::RowVectorXcd

Complex (double precision) dynamic Eigen row vector.

using cmat = Eigen::MatrixXcd

Complex (double precision) dynamic Eigen matrix.

using dmat = Eigen::MatrixXd

Real (double precision) dynamic Eigen matrix.

template<typename Scalar >

```
using dyn_mat = Eigen::Matrix < Scalar, Eigen::Dynamic, Eigen::Dynamic >
```

Dynamic Eigen matrix over the field specified by Scalar.

• template<typename Scalar >

```
using dyn_col_vect = Eigen::Matrix < Scalar, Eigen::Dynamic, 1 >
```

Dynamic Eigen column vector over the field specified by Scalar.

template<typename Scalar >

```
using dyn_row_vect = Eigen::Matrix < Scalar, 1, Eigen::Dynamic >
```

Dynamic Eigen row vector over the field specified by Scalar.

Functions

constexpr cplx operator" i (long double x) noexcept

User-defined literal for complex $i = \sqrt{-1}$ (real overload)

cplx omega (idx D)

D-th root of unity.

template<typename Derived >

dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx >
&dims)

Schmidt coefficients of the bi-partite pure state A.

• template<typename Derived >

```
dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2)
```

Schmidt coefficients of the bi-partite pure state A.

ullet template<typename Derived >

```
cmat schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
```

Schmidt basis on Alice side.

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

```
cmat schmidtA (const Eigen::MatrixBase< Derived > &A, idx d=2)
```

Schmidt basis on Alice side.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

```
cmat schmidtB (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &dims)
```

Schmidt basis on Bob side.

template<typename Derived >

```
cmat schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2)
```

Schmidt basis on Bob side.

• template<typename Derived >

```
std::vector < double > schmidtprobs (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &dims)
```

Schmidt probabilities of the bi-partite pure state A.

• template<typename Derived >

```
std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)
```

Schmidt probabilities of the bi-partite pure state A.

```
• template<typename Derived >
  double entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Entanglement of the bi-partite pure state A.

    template<typename Derived >

  double entanglement (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Entanglement of the bi-partite pure state A.

    template<typename Derived >

  double gconcurrence (const Eigen::MatrixBase< Derived > &A)
     G-concurrence of the bi-partite pure state A.
• template<typename Derived >
  double negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Negativity of the bi-partite mixed state A.

    template<typename Derived >

  double negativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Logarithmic negativity of the bi-partite mixed state A.
• template<typename Derived >
  double lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Logarithmic negativity of the bi-partite mixed state A.
• template<typename Derived >
  double concurrence (const Eigen::MatrixBase< Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.

    template<typename Derived >

  double entropy (const Eigen::MatrixBase< Derived > &A)
      von-Neumann entropy of the density matrix A

    double entropy (const std::vector< double > &prob)

     Shannon entropy of the probability distribution prob.

    template<typename Derived >

  double renyi (const Eigen::MatrixBase< Derived > &A, double alpha)
      Renyi-\alpha entropy of the density matrix A, for \alpha > 0.

    double renyi (const std::vector< double > &prob, double alpha)

     Renyi- \alpha entropy of the probability distribution prob, for \alpha > 0.
• template<typename Derived >
  double tsallis (const Eigen::MatrixBase< Derived > &A, double q)
      Tsallis- q entropy of the density matrix A, for q > 0.

    double tsallis (const std::vector< double > &prob, double q)

      Tsallis- q entropy of the probability distribution prob, for q \geq 0.
• template<typename Derived >
  double gmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx > \&subsysB, const std::vector<math>< idx > \&dims)
      Quantum mutual information between 2 subsystems of a composite system.

    template<typename Derived >

  double qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx > &subsysB, idx d=2)
      Quantum mutual information between 2 subsystems of a composite system.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > transpose (const Eigen::MatrixBase< Derived > &A)
      Transpose.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > conjugate (const Eigen::MatrixBase< Derived > &A)
     Complex conjugate.
```

```
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > adjoint (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > inverse (const Eigen::MatrixBase< Derived > &A)
     Inverse.

    template<typename Derived >

  {\tt Derived::Scalar\ trace\ (const\ Eigen::MatrixBase< Derived > \&A)}
      Trace.

    template<typename Derived >

  Derived::Scalar det (const Eigen::MatrixBase< Derived > &A)
     Determinant.

    template<typename Derived >

  Derived::Scalar logdet (const Eigen::MatrixBase< Derived > &A)
     Logarithm of the determinant.
• template<typename Derived >
  Derived::Scalar sum (const Eigen::MatrixBase< Derived > &A)
     Element-wise sum of A.

    template<typename Derived >

  Derived::Scalar prod (const Eigen::MatrixBase< Derived > &A)
      Element-wise product of A.

    template<typename Derived >

  double norm (const Eigen::MatrixBase< Derived > &A)
     Frobenius norm.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > normalize (const Eigen::MatrixBase< Derived > &A)
     Normalizes state vector (column or row vector) or density matrix.

    template<typename Derived >

  std::pair< dyn col vect< cplx >, cmat > eig (const Eigen::MatrixBase< Derived > &A)
     Full eigen decomposition.

    template<typename Derived >

  dyn_col_vect< cplx > evals (const Eigen::MatrixBase< Derived > &A)
     Eigenvalues.

    template<typename Derived >

  cmat evects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors.

    template<typename Derived >

  std::pair< dyn_col_vect< double >, cmat > heig (const Eigen::MatrixBase< Derived > &A)
     Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > hevals (const Eigen::MatrixBase< Derived > &A)
     Hermitian eigenvalues.
• template<typename Derived >
  cmat hevects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors of Hermitian matrix.

    template<typename Derived >

  std::tuple< cmat, dyn_col_vect< double >, cmat > svd (const Eigen::MatrixBase< Derived > &A)
     Full singular value decomposition.
• template<typename Derived >
  dyn_col_vect< double > svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.

    template<typename Derived >

  cmat svdU (const Eigen::MatrixBase< Derived > &A)
```

Kronecker power.

```
Left singular vectors.
• template<typename Derived >
  cmat svdV (const Eigen::MatrixBase< Derived > &A)
     Right singular vectors.
• template<typename Derived >
  cmat funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)
• template<typename Derived >
  cmat sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.

    template<typename Derived >

  cmat absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.

    template<typename Derived >

  cmat expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.

    template<typename Derived >

  cmat logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.

    template<typename Derived >

  cmat sinm (const Eigen::MatrixBase< Derived > &A)
     Matrix sin.

    template<typename Derived >

  cmat cosm (const Eigen::MatrixBase< Derived > &A)
• template<typename Derived >
  cmat spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > powm (const Eigen::MatrixBase< Derived > &A, idx n)
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.
• template<typename Derived >
  double schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
 \bullet \ \ \text{template} < \text{typename OutputScalar , typename Derived} >
  dyn_mat< OutputScalar > cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const type-
  name Derived::Scalar &))
     Functor.
• template<typename T >
  dyn_mat< typename T::Scalar > kron (const T &head)
     Kronecker product.

    template<typename T, typename... Args>

  dyn mat< typename T::Scalar > kron (const T &head, const Args &... tail)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > kron (const std::vector< Derived > &As)
     Kronecker product.
template<typename Derived >
  dyn_mat< typename Derived::Scalar > kron (const std::initializer_list< Derived > &As)
     Kronecker product.
template<typename Derived >
  dyn mat< typename Derived::Scalar > kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
```

```
• template<typename T >
  dyn_mat< typename T::Scalar > dirsum (const T &head)
• template<typename T , typename... Args>
  dyn mat< typename T::Scalar > dirsum (const T &head, const Args &... tail)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > dirsum (const std::vector< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > dirsum (const std::initializer_list< Derived > &As)
     Direct sum.
• template<typename Derived >
  dyn mat< typename Derived::Scalar > dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > reshape (const Eigen::MatrixBase< Derived > &A, idx rows, idx
  cols)
     Reshape.
 template<typename Derived1 , typename Derived2 >
  dyn_mat< typename Derived1::Scalar > comm (const Eigen::MatrixBase< Derived1 > &A, const Eigen::↔
  MatrixBase< Derived2 > &B)
     Commutator.
ullet template<typename Derived1 , typename Derived2 >
  dyn_mat< typename Derived1::Scalar > anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > prj (const Eigen::MatrixBase< Derived > &A)
     Projector.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > grams (const std::vector< Derived > &As)
     Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > grams (const std::initializer_list< Derived > &As)
     Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > grams (const Eigen::MatrixBase< Derived > &A)
     Gram-Schmidt orthogonalization.

    std::vector< idx > n2multiidx (idx n, const std::vector< idx > &dims)

     Non-negative integer index to multi-index.
• idx multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)
     Multi-index to non-negative integer index.

    ket mket (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Multi-partite qudit ket.

    ket mket (const std::vector < idx > &mask, idx d=2)

     Multi-partite qudit ket.

    cmat mprj (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Projector onto multi-partite qudit ket.

    cmat mprj (const std::vector < idx > &mask, idx d=2)

     Projector onto multi-partite qudit ket.
• template<typename InputIterator >
```

std::vector< double > abssq (InputIterator first, InputIterator last)

Computes the absolute values squared of an STL-like range of complex numbers.

• template<typename Container >

std::vector< double > abssq (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Computes the absolute values squared of an STL-like container.

• template<typename Derived >

std::vector< double > abssq (const Eigen::MatrixBase< Derived > &A)

Computes the absolute values squared of an Eigen expression.

• template<typename InputIterator >

std::iterator_traits< InputIterator >::value_type sum (InputIterator first, InputIterator last)

Element-wise sum of an STL-like range.

• template<typename Container >

Container::value_type sum (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

std::iterator_traits< InputIterator >::value_type prod (InputIterator first, InputIterator last)

Element-wise product of an STL-like range.

• template<typename Container >

Container::value_type prod (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Element-wise product of the elements of an STL-like container.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > rho2pure (const Eigen::MatrixBase< Derived > &A)

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

std::vector< idx > complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

template<typename Derived >

std::vector< double > rho2bloch (const Eigen::MatrixBase< Derived > &A)

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

template<typename Derived >

```
std::size_t hash_eigen (const Eigen::MatrixBase< Derived > &A, std::size_t seed=0)
```

Computes the hash of en Eigen matrix/vector/expression.

template<typename Derived >

internal::IOManipEigen disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)

Eigen expression ostream manipulator.

• internal::IOManipEigen disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

• template<typename InputIterator >

internal::IOManipRange< InputIterator > disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")

Range ostream manipulator.

• template<typename Container >

internal::IOManipRange< typename Container::const_iterator > disp (const Container &c, const std::string &separator, const std::string &start="[", const std::string &end="]", typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

template<typename PointerType >

internal::IOManipPointer< PointerType > disp (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")

C-style pointer ostream manipulator.

template < typename Derived > void save (const Eigen::MatrixBase < Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.

• template<typename Derived >

dyn_col_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)

Generalized inner product.

• template<typename Derived >

dyn_col_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::

MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

• template<typename Derived >

 $std::tuple < idx, std::vector < double >, std::vector < cmat > > measure (const Eigen::MatrixBase < Derived > &A, const std::initializer_list < cmat > &Ks)$

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

• template<typename Derived >

```
std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)
```

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

```
std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)
```

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

```
std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)
```

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

```
std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector< idx > &dims)
```

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

```
std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)
```

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template<typename Derived >

std::tuple< std::vector< idx >, double, cmat > measure_seq (const Eigen::MatrixBase< Derived > &A, std::vector< idx > target, idx d=2)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< cplx > >::type loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::

Scalar > >::type loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

std::vector< int > x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

• bigint gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > invperm (const std::vector< idx > &perm)

Inverse permutation.

std::vector< idx > compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

std::vector< bigint > factors (bigint a)

Prime factor decomposition.

bigint modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

• bigint modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple < bigint, bigint, bigint > egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

• bigint modiny (bigint a, bigint p)

Modular inverse of a mod p.

• bool isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

• bigint randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

std::vector< std::pair< int, int > > convergents (const std::vector< int > &cf)

Convergents.

std::vector< std::pair< int, int > > convergents (double x, idx N)

Convergents.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, const
std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, idx
d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1, typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)
```

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

• template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, const std::vector< idx > &dims)
```

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

• template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, idx d=2)
```

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat kraus2super (const std::vector< cmat > &Ks)

Superoperator matrix.

cmat kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector< cmat > choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

template<typename Derived >

```
\frac{dyn\_mat}{<} typename \ Derived::Scalar > ptrace1 \ (const \ Eigen::MatrixBase < Derived > \&A, \ const \ std \leftarrow ::vector < idx > \&dims)
```

Partial trace.

template<typename Derived >

```
\frac{\text{dyn\_mat}{<} \text{ typename Derived::} Scalar > \text{ptrace1} \text{ (const Eigen::} MatrixBase{<} \text{ Derived} > \&A, \text{idx d=2)}
```

Partial trace.

• template<typename Derived >

 dyn_mat < typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, const std \leftarrow ::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector<
idx > &target, const std::vector< idx > &dims)

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector
idx > &target, idx d=2)

Partial trace.

template<typename Derived >

Partial transpose.

ullet template<typename Derived >

dyn_mat< typename Derived::Scalar > ptranspose (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial transpose.

template<typename Derived >

Subsystem permutation.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > syspermute (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &perm, idx d=2)

Subsystem permutation.

template<typename Derived >

dyn_mat< typename Derived::Scalar > applyQFT (const Eigen::MatrixBase< Derived > &A, const std↔ ::vector< idx > &target, idx d=2, bool swap=true)

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

ullet template<typename Derived >

dyn_mat< typename Derived::Scalar > applyTFQ (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2, bool swap=true)

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Qudit quantum Fourier transform.

• double rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

• bigint rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

• idx randidx (idx a=std::numeric_limits < idx >::min(), idx b=std::numeric_limits < idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

• template<typename Derived >

Derived rand (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double a QPP_UNUSED_=0, double b QPP_UNUSED_=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

• template<>

```
dmat rand (idx rows, idx cols, double a, double b)
```

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

template<>

```
cmat rand (idx rows, idx cols, double a, double b)
```

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived randn (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double mean QPP_UNUSED_=0, double sigma QPP_UNUSED_=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

```
dmat randn (idx rows, idx cols, double mean, double sigma)
```

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

template<>

```
cmat randn (idx rows, idx cols, double mean, double sigma)
```

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

double randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

cmat randU (idx D=2)

Generates a random unitary matrix.

· cmat randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector < cmat > randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat randH (idx D=2)

Generates a random Hermitian matrix.

ket randket (idx D=2)

Generates a random normalized ket (pure state vector)

• cmat randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.

std::vector< double > uniform (idx N)

Uniform probability distribution vector.

std::vector< double > marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > marginalY (const dmat &probXY)

Marginal distribution.

• template<typename Container >

double avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Average.

template<typename Container >
 double cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if<
 is_iterable< Container >::value >::type *=nullptr)

Covariance.

• template<typename Container >

double var (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Variance.

• template<typename Container >

double sigma (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Standard deviation.

• template<typename Container >

double cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Correlation.

Variables

constexpr double chop = 1e-10

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

• constexpr idx maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

constexpr double pi = 3.141592653589793238462643383279502884

 π

• constexpr double ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

constexpr double infty = std::numeric_limits<double>::max()

Used to denote infinity in double precision.

6.1.1 Detailed Description

Quantum++ main namespace.

6.1.2 Typedef Documentation

6.1.2.1 bigint

```
using qpp::bigint = typedef long long int
```

Big integer.

```
6.1.2.2 bra
```

```
using qpp::bra = typedef Eigen::RowVectorXcd
```

Complex (double precision) dynamic Eigen row vector.

6.1.2.3 cmat

```
using qpp::cmat = typedef Eigen::MatrixXcd
```

Complex (double precision) dynamic Eigen matrix.

6.1.2.4 cplx

```
using qpp::cplx = typedef std::complex<double>
```

Complex number in double precision.

6.1.2.5 dmat

```
using qpp::dmat = typedef Eigen::MatrixXd
```

Real (double precision) dynamic Eigen matrix.

6.1.2.6 dyn_col_vect

```
template<typename Scalar >
using qpp::dyn_col_vect = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, 1>
```

Dynamic Eigen column vector over the field specified by Scalar.

Example:

```
// type of colvect is Eigen::Matrix<float, Eigen::Dynamic, 1>
dyn_col_vect<float> colvect(2);
```

6.1.2.7 dyn_mat

```
template<typename Scalar >
using qpp::dyn_mat = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, Eigen::Dynamic>
```

Dynamic Eigen matrix over the field specified by Scalar.

Example:

```
// type of mat is Eigen::Matrix<float, Eigen::Dynamic, Eigen::Dynamic>
dyn_mat<float> mat(2, 3);
```

6.1.2.8 dyn_row_vect

```
template<typename Scalar >
using qpp::dyn_row_vect = typedef Eigen::Matrix<Scalar, 1, Eigen::Dynamic>
```

Dynamic Eigen row vector over the field specified by Scalar.

Example:

```
// type of rowvect is Eigen::Matrix<float, 1, Eigen::Dynamic>
dyn_row_vect<float> rowvect(3);
```

6.1.2.9 idx

```
using qpp::idx = typedef std::size_t
```

Non-negative integer index, make sure you use an unsigned type.

6.1.2.10 ket

```
using qpp::ket = typedef Eigen::VectorXcd
```

Complex (double precision) dynamic Eigen column vector.

6.1.2.11 to_void

```
template<typename... Ts>
using qpp::to_void = typedef typename make_void<Ts...>::type
```

Alias template that implements the proposal for void_t.

See also

http://www.open-std.org/jtc1/sc22/wg21/docs/papers/2014/n3911

6.1.3 Function Documentation

6.1.3.1 absm()

Matrix absolute value.

Parameters

```
A Eigen expression
```

Returns

Matrix absolute value of A

6.1.3.2 abssq() [1/3]

Computes the absolute values squared of an STL-like range of complex numbers.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Real vector consisting of the range absolute values squared

Computes the absolute values squared of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Real vector consisting of the container's absolute values squared

Computes the absolute values squared of an Eigen expression.

Parameters

```
A Eigen expression
```

Returns

Real vector consisting of the absolute values squared

6.1.3.5 adjoint()

Adjoint.

```
A Eigen expression
```

Returns

Adjoint (Hermitian conjugate) of A, as a dynamic matrix over the same scalar field as A

6.1.3.6 anticomm()

Anti-commutator.

See also

qpp::comm()

Anti-commutator $\{A,B\} = AB + BA$. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
В	Eigen expression

Returns

Anti-commutator AB + BA, as a dynamic matrix over the same scalar field as A

6.1.3.7 apply() [1/5]

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

Returns

Gate A applied to the part target of state

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

Returns

Gate A applied to the part target of state

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes where the Kraus operators Ks are applied
dims	Dimensions of the multi-partite system

Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*.

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes where the Kraus operators Ks are applied
d	Subsystem dimensions

Returns

Output density matrix after the action of the channel

6.1.3.12 applyCTRL() [1/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate *A* must match the dimension of *target*. Also, all control subsystems in *ctrl* must have the same dimension.

Parameters

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

Returns

CTRL-A gate applied to the part target of state

6.1.3.13 applyCTRL() [2/2]

```
template<typename Derived1 , typename Derived2 > dyn_mat<typename Derived1::Scalar> qpp::applyCTRL ( const Eigen::MatrixBase< Derived1 > & state, const Eigen::MatrixBase< Derived2 > & A, const std::vector< idx > & ctrl, const std::vector< idx > & target, idx d = 2)
```

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

Returns

CTRL-A gate applied to the part target of state

6.1.3.14 applyQFT()

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

Parameters

Α	Eigen expression
target	Subsystem indexes where the QFT is applied
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Qudit Quantum Fourier transform applied to the part target of A

6.1.3.15 applyTFQ()

Applies the inverse (adjoint) qudit quantum Fourier transform to the part *target* of the multi-partite state vector or density matrix *A*.

Parameters

Α	Eigen expression
target	Subsystem indexes where the TFQ is applied
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Inverse (adjoint) qudit Quantum Fourier transform applied to the part target of A

6.1.3.16 avg()

Average.

Parameters

prob	Real probability vector representing the probability distribution of X
X	Real random variable values represented by an STL-like container

Returns

Average of X

6.1.3.17 bloch2rho()

Computes the density matrix corresponding to the 3-dimensional real Bloch vector *r*.

See also

qpp::rho2bloch()

Parameters

r 3-dimensional real vector

Returns

Qubit density matrix

6.1.3.18 choi2kraus()

Orthogonal Kraus operators from Choi matrix.

See also

qpp::kraus2choi()

Extracts a set of orthogonal (under Hilbert-Schmidt operator norm) Kraus operators from the Choi matrix A

Note

The Kraus operators satisfy $Tr(K_i^{\dagger}K_j) = \delta_{ij}$ for all $i \neq j$

Parameters

A Choi matrix

Returns

Set of orthogonal Kraus operators

6.1.3.19 choi2super()

Converts Choi matrix to superoperator matrix.

See also

qpp::super2choi()

Parameters

```
A Choi matrix
```

Returns

Superoperator matrix

6.1.3.20 comm()

Commutator.

See also

qpp::anticomm()

Commutator [A, B] = AB - BA. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
В	Eigen expression

Returns

Commutator AB-BA, as a dynamic matrix over the same scalar field as ${\it A}$

6.1.3.21 complement()

```
std::vector<idx> qpp::complement (
    std::vector< idx > subsys,
    idx n ) [inline]
```

Constructs the complement of a subsystem vector.

Parameters

subsys	Subsystem vector
n	Total number of systems

Returns

Complement of *subsys* with respect to the set $\{0,1,\ldots,n-1\}$

6.1.3.22 compperm()

Compose permutations.

Parameters

perm	Permutation
sigma	Permutation

Returns

Composition of the permutations *perm* o *sigma* = perm(sigma)

6.1.3.23 concurrence()

Wootters concurrence of the bi-partite qubit mixed state A.

Parameters

```
A Eigen expression
```

Wootters concurrence

6.1.3.24 conjugate()

Complex conjugate.

Parameters

```
A Eigen expression
```

Returns

Complex conjugate of A, as a dynamic matrix over the same scalar field as A

6.1.3.25 contfrac2x()

```
double qpp::contfrac2x ( const std::vector< int > & cf, idx N = idx(-1) ) [inline]
```

Real representation of a simple continued fraction.

See also

```
qpp::x2contfrac()
```

Note

If N is greater than the size of cf (by default it is), then all terms in cf are considered.

Parameters

Ci	•	Integer vector containing the simple continued fraction expansion
Ν		Number of terms considered in the continued fraction expansion.

Returns

Real representation of the simple continued fraction

```
6.1.3.26 convergents() [1/2]
```

```
std::vector<std::pair<int, int> > qpp::convergents ( const std::vector< int > & cf ) [inline]
```

Convergents.

See also

qpp::contfrac2x() and qpp::x2contfrac()

Parameters

```
cf Continued fraction
```

Returns

Vector of convergents pairs (a_k, b_k) that approximate the number represented by the continued fraction

6.1.3.27 convergents() [2/2]

Convergents.

See also

qpp::contfrac2x() and qpp::x2contfrac()

Note

In the continued fraction expansion of x has less terms than N, then the series of convergents is truncated to the number of terms in the continued fraction expansion of x.

Parameters

X	Real number	
Ν	Number of convergents.	

Returns

Vector of convergents pairs (a_k,b_k) that approximate the number x

6.1.3.28 cor()

Correlation.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels the rows, Y labels the columns)
Χ	Real random variable values represented by an STL-like container
Y	Real random variable values represented by an STL-like container

Returns

Correlation of X and Y

6.1.3.29 cosm()

Matrix cos.

Parameters

```
A Eigen expression
```

Returns

Matrix cosine of A

6.1.3.30 cov()

Covariance.

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels the rows, Y labels the columns)
Χ	Real random variable values represented by an STL-like container
Y	Real random variable values represented by an STL-like container

Returns

Covariance of X and Y

6.1.3.31 cwise()

Functor.

Parameters

Α	Eigen expression
f	Pointer-to-function from scalars of A to OutputScalar

Returns

Component-wise f(A), as a dynamic matrix over the ${\it OutputScalar}$ scalar field

6.1.3.32 det()

Determinant.

Parameters

```
A Eigen expression
```

Returns

Determinant of A, as a scalar over the same scalar field as A. Returns $\pm \infty$ when the determinant overflows/underflows.

Direct sum.

See also

qpp::dirsumpow()

Used to stop the recursion for the variadic template version of qpp::dirsum()

Parameters

head	Eigen expression
------	------------------

Returns

Its argument head

6.1.3.34 dirsum() [2/4]

Direct sum.

See also

qpp::dirsumpow()

Parameters

head	Eigen expression	
tail	Variadic Eigen expression (zero or more parameters)]

Returns

Direct sum of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

std::vector of Eigen expressions

Returns

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

See also

qpp::dirsumpow()

Parameters

As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}

Returns

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.3.37 dirsumpow()

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::dirsumpow (
```

```
const Eigen::MatrixBase< Derived > & A, idx n)
```

Direct sum power.

See also

qpp::dirsum()

Parameters

Α	Eigen expression
n	Non-negative integer

Returns

Direct sum of A with itself n times $A^{\oplus n}$, as a dynamic matrix over the same scalar field as A

Eigen expression ostream manipulator.

Parameters

1	4	Eigen expression
(chop	Set to zero the elements smaller in absolute value than chop

Returns

Instance of qpp::internal::IOManipEigen

Complex number ostream manipulator.

Z	Complex number (or any other type implicitly cast-able to std::complex <double>)</double>
chop	Set to zero the elements smaller in absolute value than <i>chop</i>

Returns

Instance of qpp::internal::IOManipEigen

Range ostream manipulator.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipRange

```
6.1.3.41 disp() [4/5]
```

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

С	Container
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipRange

C-style pointer ostream manipulator.

Parameters

p	Pointer to the first element
N	Number of elements to be displayed
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipPointer

6.1.3.43 egcd()

Extended greatest common divisor of two integers.

See also

qpp::gcd()

а	Integer
b	Integer

Returns

Tuple of: 1. Integer m, 2. Integer n, and 3. Non-negative integer gcd(a,b) such that ma + nb = gcd(a,b)


6.1.3.44 eig()

Full eigen decomposition.

See also

qpp::heig()

Parameters



Returns

Pair of: 1. Eigenvalues of A, as a complex dynamic column vector, and 2. Eigenvectors of A, as columns of a complex dynamic matrix

6.1.3.45 entanglement() [1/2]

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

qpp::entropy()

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Entanglement, with the logarithm in base 2

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

qpp::entropy()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Entanglement, with the logarithm in base 2

6.1.3.47 entropy() [1/2] template<typename Derived >

const Eigen::MatrixBase< Derived > & A)

von-Neumann entropy of the density matrix A

Parameters

A Eigen expression

double qpp::entropy (

von-Neumann entropy, with the logarithm in base 2

Shannon entropy of the probability distribution prob.

Parameters

```
prob Real probability vector
```

Returns

Shannon entropy, with the logarithm in base 2

6.1.3.49 evals()

Eigenvalues.

See also

qpp::hevals()

Parameters

```
A Eigen expression
```

Returns

Eigenvalues of A, as a complex dynamic column vector

6.1.3.50 evects()

Eigenvectors.

See also

qpp::hevects()

Parameters

```
A Eigen expression
```

Returns

Eigenvectors of A, as columns of a complex dynamic matrix

6.1.3.51 expm()

Matrix exponential.

Parameters

```
A Eigen expression
```

Returns

Matrix exponential of A

6.1.3.52 factors()

Prime factor decomposition.

Note

Runs in $\mathcal{O}(\sqrt{n})$ time complexity

Parameters

a Integer different from 0, 1 or -1

Integer vector containing the factors

6.1.3.53 funm()

Functional calculus f(A)

Parameters

Α	Eigen expression
f	Pointer-to-function from complex to complex

Returns

f(A)

Greatest common divisor of two integers.

See also

qpp::lcm()

Parameters

а	Integer
b	Integer

Returns

Greatest common divisor of a and b

```
6.1.3.55 gcd() [2/2]
bigint qpp::gcd (
              const std::vector< bigint > \& as ) [inline]
Greatest common divisor of a list of integers.
See also
     qpp::lcm()
Parameters
 as List of integers
Returns
     Greatest common divisor of all numbers in as
6.1.3.56 gconcurrence()
template<typename Derived >
double qpp::gconcurrence (
              const Eigen::MatrixBase< Derived > & A )
G-concurrence of the bi-partite pure state A.
Note
     Both local dimensions must be equal
Uses qpp::logdet() to avoid overflows
See also
     qpp::logdet()
Parameters
     Eigen expression
```

G-concurrence

Gram-Schmidt orthogonalization.

Parameters

As std::vector of Eigen expressions as column vectors

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

Gram-Schmidt orthogonalization.

Parameters

As std::initializer_list of Eigen expressions as column vectors

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

Gram-Schmidt orthogonalization.

Parameters

A | Eigen expression, the input vectors are the columns of A

Gram-Schmidt vectors of the columns of A, as columns of a dynamic matrix over the same scalar field as A

6.1.3.60 hash_eigen()

Computes the hash of en Eigen matrix/vector/expression.

Note

Code taken from boost::hash_combine(), see https://www.boost.org/doc/libs/1_69_← 0/doc/html/hash/reference.html#boost.hash_combine

Parameters

Α	Eigen expression
seed	Seed, 0 by default

Returns

Hash of its argument

6.1.3.61 heig()

Full eigen decomposition of Hermitian expression.

See also

qpp::eig()

Parameters

A Eigen expression

Pair of: 1. Eigenvalues of A, as a real dynamic column vector, and 2. Eigenvectors of A, as columns of a complex dynamic matrix

6.1.3.62 hevals()

Hermitian eigenvalues.

See also

qpp::evals()

Parameters

A Eigen expression

Returns

Eigenvalues of Hermitian A, as a real dynamic column vector

6.1.3.63 hevects()

Eigenvectors of Hermitian matrix.

See also

qpp::evects()

Parameters

A Eigen expression

Returns

Eigenvectors of Hermitian matrix A, as columns of a complex matrix

6.1.3.64 inverse()

Inverse.

Parameters

```
A Eigen expression
```

Returns

Inverse of A, as a dynamic matrix over the same scalar field as A

6.1.3.65 invperm()

```
\label{eq:std:vector} $$ std::vector < idx > & perm ) $$ [inline] $$
```

Inverse permutation.

Parameters

perm	Permutation
------	-------------

Returns

Inverse of the permutation perm

6.1.3.66 ip() [1/2]

Generalized inner product.

Parameters

phi	Column vector Eigen expression
psi	Column vector Eigen expression
subsys	Subsystem indexes over which phi is defined
dims	Dimensions of the multi-partite system

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

Generalized inner product.

Parameters

phi	Column vector Eigen expression
psi	Column vector Eigen expression
subsys	Subsystem indexes over which phi is defined
d	Subsystem dimensions

Returns

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

6.1.3.68 isprime()

Primality test based on the Miller-Rabin's algorithm.

Parameters

р	Integer different from 0, 1 or -1
k	Number of iterations. The probability of a false positive is 2^{-k} .

Returns

True if the number is (most-likely) prime, false otherwise

6.1.3.69 kraus2choi()

Choi matrix.

See also

qpp::choi2kraus()

Constructs the Choi matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|$, $|0\rangle\langle 1|$ etc.

Note

The superoperator matrix S and the Choi matrix C are related by $S_{ab,mn}=C_{ma,nb}$

Parameters

Ks Set of Kraus operators

Returns

Choi matrix

6.1.3.70 kraus2super()

Superoperator matrix.

Constructs the superoperator matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|$, $|0\rangle\langle 1|$ etc.

Parameters

Ks Set of Kraus operators

Returns

Superoperator matrix

Kronecker product.

See also

qpp::kronpow()

Used to stop the recursion for the variadic template version of app::kron()

Parameters

head	Eigen expression
------	------------------

Returns

Its argument head

```
6.1.3.72 kron() [2/4]
```

Kronecker product.

See also

qpp::kronpow()

Parameters

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

Returns

Kronecker product of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

As std::vector of Eigen expressions

Returns

Kronecker product of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Kronecker product.

See also

qpp::kronpow()

Parameters

As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}

Returns

Kronecker product of all elements in *As*, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.3.75 kronpow()

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::kronpow (
```

```
const Eigen::MatrixBase< Derived > & A, idx n)
```

Kronecker power.

See also

qpp::kron()

Parameters

Α	Eigen expression
n	Non-negative integer

Returns

Kronecker product of A with itself n times $A^{\otimes n}$, as a dynamic matrix over the same scalar field as A

Least common multiple of two integers.

See also

qpp::gcd()

Parameters

а	Integer
b	Integer

Returns

Least common multiple of a and b

Least common multiple of a list of integers.

See also

```
qpp::gcd()
```

Parameters

```
as List of integers
```

Returns

Least common multiple of all numbers in as

6.1.3.78 load()

Loads Eigen matrix from a binary file (internal format) in double precision.

See also

qpp::save()

The template parameter cannot be automatically deduced and must be explicitly provided, depending on the scalar field of the matrix that is being loaded.

Example:

```
// loads a previously saved Eigen dynamic complex matrix from "input.bin" cmat mat = load<cmat>("input.bin");
```

Parameters

```
fname Output file name
```

6.1.3.79 loadMATLAB() [1/2]

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

```
qpp::saveMATLAB()
```

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen ket
// from the MATLAB file "input.mat"
ket psi = loadMATLABket>("input.mat");
```

Template Parameters

Derived	Complex Eigen type
---------	--------------------

Parameters

mat_file	MATALB .mat file	
var_name	Variable name in the .mat file representing the matrix to be loaded	

Returns

Eigen dynamic matrix

6.1.3.80 loadMATLAB() [2/2]

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

```
qpp::saveMATLAB()
```

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen dynamic double matrix
// from the MATLAB file "input.mat"
dmat mat = loadMATLAB<dmat>("input.mat");
```

Template Parameters

Derived Non-complex Eigen type	
--------------------------------	--

Parameters

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be loaded

Returns

Eigen dynamic matrix

6.1.3.81 logdet()

Logarithm of the determinant.

Useful when the determinant overflows/underflows

Parameters

```
A Eigen expression
```

Returns

Logarithm of the determinant of A, as a scalar over the same scalar field as A

6.1.3.82 logm()

Matrix logarithm.

Parameters

A Eigen expression

Matrix logarithm of A

Logarithmic negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Logarithmic negativity, with the logarithm in base 2

6.1.3.84 lognegativity() [2/2]

```
template<typename Derived >
double qpp::lognegativity (
    const Eigen::MatrixBase< Derived > & A,
    idx d = 2 )
```

Logarithmic negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Logarithmic negativity, with the logarithm in base 2

6.1.3.85 marginalX()

Marginal distribution.

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels	1
	the rows, Y labels the columns)	

Returns

Real vector consisting of the marginal distribution of X

6.1.3.86 marginalY()

Marginal distribution.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels
	the rows, Y labels the columns)

Returns

Real vector consisting of the marginal distribution of Y

6.1.3.87 measure() [1/9]

Measures the state vector or density operator A using the set of Kraus operators Ks.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.88 measure() [2/9]

Measures the state vector or density matrix A using the set of Kraus operators Ks.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.89 measure() [3/9]

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

Parameters

	Α	Eigen expression
ſ	U	Unitary matrix whose columns represent the measurement basis vectors

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.90 measure() [4/9]

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.91 measure() [5/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.93 measure() [7/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.94 measure() [8/9]

Measures the part *target* of the multi-partite state vector or density matrix *A* in the orthonormal basis or rank-1 projectors specified by the columns of the matrix *V*.

See also

```
qpp::measure_seq()
```

Note

The dimension of *V* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Α	Eigen expression
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part *target* of the multi-partite state vector or density matrix *A* in the orthonormal basis or rank-1 projectors specified by the columns of the matrix *V*.

See also

```
qpp::measure_seq()
```

Note

The dimension of *V* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression	
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors	
target	Subsystem indexes that are measured	
d	Subsystem dimensions	

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

See also

qpp::measure()

Parameters

Α	Eigen expression
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

See also

qpp::measure()

Parameters

Α	Eigen expression
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|\text{mask}\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

Parameters

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

Returns

Multi-partite qudit state vector, as a complex dynamic column vector

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Multi-partite qudit state vector, as a complex dynamic column vector

6.1.3.100 modinv()

Modular inverse of a mod p.

See also

```
qpp::egcd()
```

Note

a and p must be co-prime

Parameters

а	Non-negative integer
р	Non-negative integer

Returns

```
Modular inverse a^{-1} \mod p
```

6.1.3.101 modmul()

Modular multiplication without overflow.

Computes $ab \bmod p$ without overflow

Parameters

а	Integer
b	Integer
р	Positive integer

Returns

 $ab \bmod p$ avoiding overflow

6.1.3.102 modpow()

```
bigint qpp::modpow (
          bigint a,
```

```
bigint n,
bigint p ) [inline]
```

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

Note

Uses qpp::modmul() that avoids overflows

Computes $a^n \bmod p$

Parameters

а	Non-negative integer	
n	Non-negative integer	
р	Strictly positive integer	

Returns

```
a^n \bmod p
```

```
6.1.3.103 mprj() [1/2]

cmat qpp::mprj (
```

const std::vector< idx > & mask,

const std::vector< idx > & dims) [inline]

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

Parameters

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

6.1.3.105 multiidx2n()

Multi-index to non-negative integer index.

See also

```
qpp::n2multiidx()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

Parameters

midx	Multi-index
dims	Dimensions of the multi-partite system

Returns

Non-negative integer index

6.1.3.106 n2multiidx()

```
\label{eq:std::vector} $$ std::vector < idx > qpp::n2multiidx ($$ idx n,$$ const std::vector < idx > & dims ) [inline]
```

Non-negative integer index to multi-index.

See also

```
qpp::multiidx2n()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

Parameters

n	Non-negative integer index	
dims	Dimensions of the multi-partite system	

Returns

Multi-index of the same size as dims

6.1.3.107 negativity() [1/2]

Negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Negativity

6.1.3.108 negativity() [2/2]

```
template<typename Derived >
double qpp::negativity (
```

```
const Eigen::MatrixBase< Derived > & A, idx d = 2)
```

Negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Negativity

6.1.3.109 norm()

Frobenius norm.

Parameters

```
A Eigen expression
```

Returns

Frobenius norm of A

6.1.3.110 normalize()

Normalizes state vector (column or row vector) or density matrix.

Parameters

A Eigen expression

Normalized state vector or density matrix

D-th root of unity.

Parameters

D Non-negative integer

Returns

D-th root of unity $\exp(2\pi i/D)$

User-defined literal for complex $i = \sqrt{-1}$ (real overload)

Example:

```
cplx z = 4.5_i; // type of z is std::complex<double>
```

6.1.3.113 powm()

Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

See also

```
qpp::spectralpowm()
```

Explicitly multiplies the matrix A with itself n times. By convention $A^0 = I$.

Parameters

Α	Eigen expression
n	Non-negative integer

Returns

Matrix power A^n , as a dynamic matrix over the same scalar field as A

6.1.3.114 prj()

Projector.

Normalized projector onto state vector

Parameters

```
A Eigen expression
```

Returns

Projector onto the state vector A, or the matrix Zero if A has norm zero, as a dynamic matrix over the same scalar field as A

6.1.3.115 prod() [1/3]

Element-wise product of A.

Parameters

```
A Eigen expression
```

Returns

Element-wise product of A, as a scalar over the same scalar field as A

Element-wise product of an STL-like range.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Element-wise product of the range, as a scalar over the same scalar field as the range

Element-wise product of the elements of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Element-wise product of the elements of the container, as a scalar over the same scalar field as the container

Partial trace.

See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Returns

Partial trace $Tr_{subsys}(\cdot)$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

Partial trace.

See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial trace $Tr_{subsys}(\cdot)$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

```
6.1.3.120 ptrace1() [1/2]
```

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_A(\cdot)$ over the first subsytem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.121 ptrace1() [2/2]

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_A(\cdot)$ over the first subsystem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.122 ptrace2() [1/2]

Partial trace.

See also

```
qpp::ptrace1()
```

Partial trace over the second subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_B(\cdot)$ over the second subsytem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.123 ptrace2() [2/2]

Partial trace.

See also

qpp::ptrace1()

Partial trace over the second subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_B(\cdot)$ over the second subsytem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.124 ptranspose() [1/2]

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::ptranspose (
```

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & target,
const std::vector< idx > & dims )
```

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.3.125 ptranspose() [2/2]

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.3.126 QFT()

```
template<typename Derived >
dyn_col_vect<typename Derived::Scalar> qpp::QFT (
```

```
const Eigen::MatrixBase< Derived > & A, idx d = 2, bool swap = true)
```

Qudit quantum Fourier transform.

Parameters

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Qudit quantum Fourier transform applied on A

6.1.3.127 qmutualinfo() [1/2]

Quantum mutual information between 2 subsystems of a composite system.

Parameters

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
dims	Dimensions of the multi-partite system

Returns

Mutual information between the 2 subsystems

6.1.3.128 qmutualinfo() [2/2]

Quantum mutual information between 2 subsystems of a composite system.

Parameters

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
d	Subsystem dimensions

Returns

Mutual information between the 2 subsystems

Generates a random real number uniformly distributed in the interval [a, b)

Parameters

а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Returns

Random real number (double) uniformly distributed in the interval [a, b)

Generates a random big integer uniformly distributed in the interval [a, b].

Note

To avoid ambiguity with double qpp::rand(double, double) cast at least one of the arguments to qpp::bigint

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

Random big integer uniformly distributed in the interval [a, b]

Generates a random matrix with entries uniformly distributed in the interval [a, b)

If complex, then both real and imaginary parts are uniformly distributed in [a, b)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

```
6.1.3.132 rand() [4/5]

template<>>
dmat qpp::rand (
        idx rows ,
        idx cols ,
        double a ,
        double b ) [inline]
```

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries uniformly distributed in [-1,1)
dmat mat = rand<dmat>(3, 3, -1, 1);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Random real matrix

```
6.1.3.133 rand() [5/5]

template<>>
cmat qpp::rand (
        idx rows ,
        idx cols ,
        double a ,
        double b ) [inline]
```

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd,
// with entries (both real and imaginary) uniformly distributed in [-1,1)
cmat mat = rand<cmat>(3, 3, -1, 1);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Returns

Random complex matrix

6.1.3.134 randH()

```
cmat qpp::randH (
    idx D = 2) [inline]
```

Generates a random Hermitian matrix.

Parameters

D Dimension of the Hilbert space

Random Hermitian matrix

6.1.3.135 randidx()

```
idx qpp::randidx (
        idx a = std::numeric_limits<idx>::min(),
        idx b = std::numeric_limits<idx>::max() ) [inline]
```

Generates a random index (idx) uniformly distributed in the interval [a, b].

Parameters

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

Returns

Random index (idx) uniformly distributed in the interval [a, b]

6.1.3.136 randket()

```
ket qpp::randket (
idx D = 2) [inline]
```

Generates a random normalized ket (pure state vector)

Parameters

D Dimension of the Hilbert space

Returns

Random normalized ket

6.1.3.137 randkraus()

```
std::vector<cmat> qpp::randkraus (
    idx N,
    idx D = 2 ) [inline]
```

Generates a set of random Kraus operators.

Note

The set of Kraus operators satisfy the closure condition $\sum_i K_i^\dagger K_i = I$

Parameters

N	Number of Kraus operators
D	Dimension of the Hilbert space

Returns

Set of N Kraus operators satisfying the closure condition

Generates a random matrix with entries normally distributed in N(mean, sigma)

If complex, then both real and imaginary parts are normally distributed in N(mean, sigma)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries normally distributed in N(0,2)
dmat mat = randn<dmat>(3, 3, 0, 2);
```

Parameters

rows	Number of rows of the random generated matrix	
cols	Number of columns of the random generated matrix	
mean	Mean	
sigma	Standard deviation	

Returns

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd, 
// with entries (both real and imaginary) normally distributed in N(0,2) cmat mat = randn<cmat>(3, 3, 0, 2);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Returns

Random complex matrix

Generates a random real number (double) normally distributed in N(mean, sigma)

Parameters

mean	Mean
sigma	Standard deviation

Returns

Random real number normally distributed in N(mean, sigma)

6.1.3.142 randperm()

```
std::vector<idx> qpp::randperm (
    idx N ) [inline]
```

Generates a random uniformly distributed permutation.

Uses Knuth shuffle method (as implemented by std::shuffle), so that all permutations are equally probable

Parameters

```
N Size of the permutation
```

Returns

Random permutation of size N

6.1.3.143 randprime()

```
bigint qpp::randprime (
          bigint a,
          bigint b,
          idx N = 1000 ) [inline]
```

Generates a random big prime uniformly distributed in the interval [a, b].

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it
N	Maximum number of candidates

Random big integer uniformly distributed in the interval [a, b]

6.1.3.144 randprob()

```
\begin{tabular}{ll} \tt std::vector<double> qpp::randprob ( & idx N) & [inline] \end{tabular}
```

Generates a random probability vector uniformly distributed over the probability simplex.

Parameters

N Size of the probability vector

Returns

Random probability vector

6.1.3.145 randrho()

```
cmat qpp::randrho (
    idx D = 2) [inline]
```

Generates a random density matrix.

Parameters

D Dimension of the Hilbert space

Returns

Random density matrix

6.1.3.146 randU()

```
cmat qpp::randU (
    idx D = 2) [inline]
```

Generates a random unitary matrix.

Parameters

D Dimension of the Hilbert space

Returns

Random unitary

6.1.3.147 randV()

Generates a random isometry matrix.

Parameters

Din	Size of the input Hilbert space
Dout	Size of the output Hilbert space

Returns

Random isometry matrix

```
6.1.3.148 renyi() [1/2]
```

Renyi- α entropy of the density matrix A, for $\alpha \geq 0.$

Note

When $\alpha \to 1$ the Renyi entropy converges to the von-Neumann entropy, with the logarithm in base 2

Α	Eigen expression
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

Renyi- α entropy, with the logarithm in base 2

Renyi- α entropy of the probability distribution *prob*, for $\alpha \geq 0$.

Note

When $\alpha \to 1$ the Renyi entropy converges to the Shannon entropy, with the logarithm in base 2

Parameters

prob	Real probability vector	
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$	

Returns

Renyi- α entropy, with the logarithm in base 2

6.1.3.150 reshape()

Reshape.

Uses column-major order when reshaping (same as MATLAB)

Α	Eigen expression
rows	Number of rows of the reshaped matrix
cols	Number of columns of the reshaped matrix

Reshaped matrix with rows rows and cols columns, as a dynamic matrix over the same scalar field as A

6.1.3.151 rho2bloch()

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

See also

qpp::bloch2rho()

Note

It is implicitly assumed that the density matrix is Hermitian

Parameters

```
A Eigen expression
```

Returns

3-dimensional Bloch vector

6.1.3.152 rho2pure()

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

Note

No purity check is done, the input state A must have rank one, otherwise the function returns the first non-zero eigenvector of A

Parameters

A Eigen expression, assumed to be proportional to a projector onto a pure state, i.e. A is assumed to have rank one

The unique non-zero eigenvector of A (up to a phase), as a dynamic column vector over the same scalar field as A

6.1.3.153 save()

Saves Eigen expression to a binary file (internal format) in double precision.

See also

qpp::load()

Parameters

Α	Eigen expression
fname	Output file name

6.1.3.154 saveMATLAB() [1/2]

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

qpp::loadMATLAB()

Template Parameters

Complex Eigen type

Α	Eigen expression over the complex field
---	---

Parameters

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be saved
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details

6.1.3.155 saveMATLAB() [2/2]

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

qpp::loadMATLAB()

Template Parameters

igen type

Parameters

Α	Non-complex Eigen expression
mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be saved
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details

6.1.3.156 schatten()

Schatten matrix norm.

	Α	Eigen expression
ſ	р	Real number, greater or equal to 1, use qpp::infty for $p = \infty$

Schatten-p matrix norm of A

Schmidt basis on Alice side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix \boldsymbol{U} whose columns represent the Schmidt basis vectors on Alice side.

Schmidt basis on Alice side.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix U whose columns represent the Schmidt basis vectors on Alice side.

6.1.3.159 schmidtB() [1/2] template<typename Derived > cmat qpp::schmidtB (

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & dims )
```

Schmidt basis on Bob side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

Schmidt basis on Bob side.

idx d = 2)

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.162 schmidtcoeffs() [2/2]

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.163 schmidtprobs() [1/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.3.164 schmidtprobs() [2/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.3.165 sigma()

Standard deviation.

Parameters

prob	Real probability vector representing the probability distribution of X
X	Real random variable values represented by an STL-like container

Returns

Standard deviation of X

6.1.3.166 sinm()

Matrix sin.

Parameters

A Eigen expression

Returns

Matrix sine of A

6.1.3.167 spectralpowm()

Matrix power.

See also

qpp::powm()

Uses the spectral decomposition of \emph{A} to compute the matrix power. By convention $\emph{A}^0 = \emph{I}$.

Parameters

Α	Eigen expression	
Z	Complex number	

Returns

Matrix power A^z

6.1.3.168 sqrtm()

Matrix square root.

Parameters

```
A Eigen expression
```

Returns

Matrix square root of A

```
6.1.3.169 sum() [1/3]
```

Element-wise sum of A.

Parameters

```
A Eigen expression
```

Returns

Element-wise sum of A, as a scalar over the same scalar field as A

```
6.1.3.170 sum() [2/3]
```

Element-wise sum of an STL-like range.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Element-wise sum of the range, as a scalar over the same scalar field as the range

Element-wise sum of the elements of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Element-wise sum of the elements of the container, as a scalar over the same scalar field as the container

6.1.3.172 super2choi()

Converts superoperator matrix to Choi matrix.

See also

qpp::choi2super()

Parameters

A Superoperator matrix

Returns

Choi matrix

6.1.3.173 svals()

Singular values.

Parameters

A Eigen expression

Returns

Singular values of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.174 svd()

Full singular value decomposition.

Parameters

A Eigen expression

Returns

Tuple of: 1. Left sigular vectors of A, as columns of a complex dynamic matrix, 2. Singular values of A, ordered in decreasing order, as a real dynamic column vector, and 3. Right singular vectors of A, as columns of a complex dynamic matrix

6.1.3.175 svdU()

Left singular vectors.

Parameters

```
A Eigen expression
```

Returns

Complex dynamic matrix, whose columns are the left singular vectors of A

6.1.3.176 svdV()

Right singular vectors.

Parameters

```
A Eigen expression
```

Returns

Complex dynamic matrix, whose columns are the right singular vectors of A

6.1.3.177 syspermute() [1/2]

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Parameters

Α	Eigen expression
perm	Permutation
dims	Dimensions of the multi-partite system

Returns

Permuted system, as a dynamic matrix over the same scalar field as A

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Parameters

Α	Eigen expression	
perm	Permutation	
d	Subsystem dimensions	

Returns

Permuted system, as a dynamic matrix over the same scalar field as A

6.1.3.179 TFQ()

Inverse (adjoint) qudit quantum Fourier transform.

Parameters

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Inverse (adjoint) qudit quantum Fourier transform applied on A

6.1.3.180 trace()

Trace.

Parameters

```
A Eigen expression
```

Returns

Trace of A, as a scalar over the same scalar field as A

6.1.3.181 transpose()

Transpose.

Parameters

```
A Eigen expression
```

Returns

Transpose of A, as a dynamic matrix over the same scalar field as A

```
6.1.3.182 tsallis() [1/2] template<typename Derived > double qpp::tsallis ( const Eigen::MatrixBase< Derived > & A, double q)
```

Tsallis- q entropy of the density matrix A, for $q \ge 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the von-Neumann entropy, with the logarithm in base e

Parameters

Α	Eigen expression		
q	Non-negative real number		

Returns

Tsallis- q entropy

Tsallis- q entropy of the probability distribution *prob*, for $q \ge 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the Shannon entropy, with the logarithm in base e

Parameters

prob	Real probability vector
q	Non-negative real number

Returns

Tsallis- q entropy

6.1.3.184 uniform()

```
std::vector<double> qpp::uniform (
    idx N ) [inline]
```

Uniform probability distribution vector.

Parameters

N Size of the alphabet

Returns

Real vector consisting of a uniform distribution of size N

6.1.3.185 var()

Variance.

Parameters

prob	Real probability vector representing the probability distribution of X
Χ	Real random variable values represented by an STL-like container

Returns

Variance of X

6.1.3.186 x2contfrac()

Simple continued fraction expansion.

See also

```
qpp::contfrac2x()
```

Parameters

Х	Real number
Ν	Maximum number of terms in the expansion
cut	Stop the expansion when the next term is greater than cut

Returns

Integer vector containing the simple continued fraction expansion of x. If there are M less than N terms in the expansion, a shorter vector with M components is returned.

6.1.4 Variable Documentation

6.1.4.1 chop

```
constexpr double qpp::chop = 1e-10
```

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

6.1.4.2 ee

```
constexpr double qpp::ee = 2.718281828459045235360287471352662497
```

Base of natural logarithm, e.

6.1.4.3 infty

```
constexpr double qpp::infty = std::numeric_limits<double>::max()
```

Used to denote infinity in double precision.

6.1.4.4 maxn

```
constexpr idx qpp::maxn = 64
```

Maximum number of allowed qubits/qudits (subsystems)

Used internally to allocate arrays on the stack (for performance reasons):

6.1.4.5 pi

```
constexpr double qpp::pi = 3.141592653589793238462643383279502884 \pi
```

6.2 qpp::exception Namespace Reference

Quantum++ exception hierarchy namespace.

Classes

class CustomException

Custom exception.

· class DimsInvalid

Invalid dimension(s) exception.

· class DimsMismatchCvector

Dimension(s) mismatch column vector size exception.

· class DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

· class DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

· class DimsMismatchVector

Dimension(s) mismatch vector size exception.

· class DimsNotEqual

Dimensions not equal exception.

class Duplicates

System (e.g. std::vector) has duplicates exception.

class Exception

Base class for generating Quantum++ custom exceptions.

· class InvalidIterator

Invalid iterator.

class MatrixMismatchSubsys

Matrix mismatch subsystems exception.

class MatrixNotCvector

Matrix is not a column vector exception.

class MatrixNotRvector

Matrix is not a row vector exception.

class MatrixNotSquare

Matrix is not square exception.

class MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

class MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

class MatrixNotSquareNorVector

Matrix is not square nor vector exception.

class MatrixNotVector

Matrix is not a vector exception.

class NoCodeword

Codeword does not exist exception.

· class NotBipartite

Not bi-partite exception.

class NotImplemented

Code not yet implemented.

class NotQubitCvector

Column vector is not 2 x 1 exception.

class NotQubitMatrix

Matrix is not 2 x 2 exception.

class NotQubitRvector

Row vector is not 1 x 2 exception.

class NotQubitSubsys

Subsystems are not qubits exception.

· class NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

class OutOfRange

Argument out of range exception.

class PermInvalid

Invalid permutation exception.

class PermMismatchDims

Permutation mismatch dimensions exception.

· class QuditAlreadyMeasured

Qudit was already measured exception.

· class SizeMismatch

Size mismatch exception.

· class SubsysMismatchDims

Subsystems mismatch dimensions exception.

class TypeMismatch

Type mismatch exception.

class UndefinedType

Not defined for this type exception.

· class Unknown

Unknown exception.

· class ZeroSize

Object has zero size exception.

6.2.1 Detailed Description

Quantum++ exception hierarchy namespace.

6.3 qpp::experimental Namespace Reference

Experimental/test functions/classes, do not use or modify.

6.3.1 Detailed Description

Experimental/test functions/classes, do not use or modify.

6.4 qpp::internal Namespace Reference

Internal utility functions, do not use them directly or modify them.

Classes

- struct Display_Impl_
- · class EqualEigen

Functor for comparing Eigen expressions for equality.

· class HashEigen

Functor for hashing Eigen expressions.

- class IOManipEigen
- class IOManipPointer
- · class IOManipRange
- · class Singleton

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Functions

- template < class T >
 void hash combine (std::size t &seed, const T &v)
- void n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- template<typename Derived >

bool check square mat (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool check vector (const Eigen::MatrixBase< Derived > &A)

ullet template<typename Derived >

bool check_rvector (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

bool check_cvector (const Eigen::MatrixBase< Derived > &A)

• template<typename T >

bool check_nonzero_size (const T &x) noexcept

• template<typename T1 , typename T2 >

bool check_matching_sizes (const T1 &lhs, const T2 &rhs) noexcept

- bool check_dims (const std::vector < idx > &dims)
- $\bullet \ \ \mathsf{template} \mathord{<} \mathsf{typename} \ \mathsf{Derived} >$

bool check_dims_match_mat (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

 $\bullet \;\; {\sf template}{<} {\sf typename \; Derived} >$

bool check_dims_match_cvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

ullet template<typename Derived >

bool check_dims_match_rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- bool check_eq_dims (const std::vector< idx > &dims, idx dim) noexcept
- bool check_no_duplicates (std::vector < idx > v)
- bool check_subsys_match_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)
- template<typename Derived >

bool check_qubit_matrix (const Eigen::MatrixBase< Derived > &A) noexcept

• template<typename Derived >

bool check_qubit_cvector (const Eigen::MatrixBase< Derived > &A) noexcept

template<typename Derived >

bool check_qubit_rvector (const Eigen::MatrixBase< Derived > &A) noexcept

• template<typename Derived >

 $bool\ check_qubit_vector\ (const\ Eigen::MatrixBase < Derived > \&A)\ no except$

- bool check_perm (const std::vector< idx > &perm)
- template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > kron2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::
 MatrixBase< Derived2 > &B)

```
    template<typename Derived1 , typename Derived2 > dyn_mat< typename Derived1::Scalar > dirsum2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen → ::MatrixBase< Derived2 > &B)
    template<typename T > void variadic_vector_emplace (std::vector< T > &)
    template<typename T , typename First , typename... Args> void variadic_vector_emplace (std::vector< T > &v, First &&first, Args &&... args)
    idx get_num_subsys (idx D, idx d)
```

6.4.1 Detailed Description

idx get_dim_subsys (idx sz, idx N)

Internal utility functions, do not use them directly or modify them.

6.4.2 Function Documentation

6.4.2.1 check_cvector()

6.4.2.2 check_dims()

```
bool qpp::internal::check_dims (  \mbox{const std::vector} < \mbox{idx} > \& \mbox{dims} \mbox{)} \quad \mbox{[inline]}
```

6.4.2.3 check_dims_match_cvect()

6.4.2.4 check_dims_match_mat()

```
6.4.2.5 check_dims_match_rvect()
```

```
template<typename Derived >
bool qpp::internal::check_dims_match_rvect (
             const std::vector< idx > & dims,
             const Eigen::MatrixBase< Derived > & A )
6.4.2.6 check_eq_dims()
bool qpp::internal::check_eq_dims (
            const std::vector< idx > & dims,
             idx dim ) [inline], [noexcept]
6.4.2.7 check_matching_sizes()
template<typename T1 , typename T2 >
bool qpp::internal::check_matching_sizes (
            const T1 & lhs,
            const T2 & rhs ) [noexcept]
6.4.2.8 check_no_duplicates()
bool qpp::internal::check_no_duplicates (
             std::vector < idx > v) [inline]
6.4.2.9 check_nonzero_size()
template<typename T >
bool qpp::internal::check_nonzero_size (
            const T & x ) [noexcept]
6.4.2.10 check_perm()
bool qpp::internal::check_perm (
```

const std::vector< idx > & perm) [inline]

6.4.2.11 check_qubit_cvector()

```
template<typename Derived >
bool qpp::internal::check_qubit_cvector (
             const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.12 check_qubit_matrix()
template<typename Derived >
bool qpp::internal::check_qubit_matrix (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.13 check_qubit_rvector()
template<typename Derived >
bool qpp::internal::check_qubit_rvector (
             const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.14 check_qubit_vector()
template < typename Derived >
bool qpp::internal::check_qubit_vector (
             const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.15 check_rvector()
template<typename Derived >
bool qpp::internal::check_rvector (
             const Eigen::MatrixBase< Derived > & A )
6.4.2.16 check_square_mat()
template < typename Derived >
bool qpp::internal::check_square_mat (
            const Eigen::MatrixBase< Derived > & A )
```

```
6.4.2.17 check_subsys_match_dims()
```

```
bool qpp::internal::check_subsys_match_dims (
            const std::vector< idx > & subsys,
            const std::vector< idx > & dims ) [inline]
6.4.2.18 check_vector()
template<typename Derived >
bool qpp::internal::check_vector (
            const Eigen::MatrixBase< Derived > & A )
6.4.2.19 dirsum2()
template<typename Derived1 , typename Derived2 >
dyn_mat<typename Derived1::Scalar> qpp::internal::dirsum2 (
            const Eigen::MatrixBase< Derived1 > & A,
            const Eigen::MatrixBase< Derived2 > & B )
6.4.2.20 get_dim_subsys()
idx qpp::internal::get_dim_subsys (
            idx sz,
            idx N ) [inline]
6.4.2.21 get_num_subsys()
idx qpp::internal::get_num_subsys (
            idx D,
            idx d ) [inline]
6.4.2.22 hash_combine()
template<class T >
void qpp::internal::hash_combine (
            std::size_t & seed,
            const T & v )
```

6.4.2.23 kron2()

```
template<typename Derived1 , typename Derived2 >
dyn_mat<typename Derived1::Scalar> qpp::internal::kron2 (
             const Eigen::MatrixBase< Derived1 > & A,
             const Eigen::MatrixBase< Derived2 > & B )
6.4.2.24 multiidx2n()
idx qpp::internal::multiidx2n (
             const idx *const midx,
             idx numdims,
             const idx *const dims ) [inline], [noexcept]
6.4.2.25 n2multiidx()
void qpp::internal::n2multiidx (
             idx n,
             idx numdims,
             const idx *const dims,
             idx * result ) [inline], [noexcept]
6.4.2.26 variadic_vector_emplace() [1/2]
template<typename T >
void qpp::internal::variadic_vector_emplace (
            std::vector< T > & )
6.4.2.27 variadic_vector_emplace() [2/2]
template<typename T , typename First , typename... Args>
void qpp::internal::variadic_vector_emplace (
             std::vector< T > & v,
             First && first,
             Args &&... args )
```

6.5 qpp::literals Namespace Reference

Functions

```
• constexpr cplx operator"" _i (unsigned long long int x) noexcept \textit{User-defined literal for complex } i = \sqrt{-1} \textit{ (integer overload)}
```

```
template<char... Bits>
ket operator"" _ket ()
```

Multi-partite qubit ket user-defined literal.

template<char... Bits> bra operator"" _bra ()

Multi-partite qubit bra user-defined literal.

template<char... Bits> cmat operator"" _prj ()

Multi-partite qubit projector user-defined literal.

6.5.1 Function Documentation

```
6.5.1.1 operator"""_bra()

template<char... Bits>
bra qpp::literals::operator"" _bra ( )
```

Multi-partite qubit bra user-defined literal.

See also

```
qpp::mket() and qpp::adjoint()
```

Constructs the multi-partite qubit bra $\langle \mathrm{Bits}|$

Template Parameters

```
Bits String of binary numbers representing the qubit bra
```

Returns

Multi-partite qubit bra, as a complex dynamic row vector

User-defined literal for complex $i = \sqrt{-1}$ (integer overload)

Example:

```
cplx z = 4_i; // type of z is std::complex<double>
```

6.5.1.3 operator""" _ket()

```
template<char... Bits>
ket qpp::literals::operator"" _ket ( )
```

Multi-partite qubit ket user-defined literal.

See also

qpp::mket()

Constructs the multi-partite qubit ket $|Bits\rangle$

Template Parameters

Bits	String of binary numbers representing the qubit ket
------	---

Returns

Multi-partite qubit ket, as a complex dynamic column vector

6.5.1.4 operator""" _prj()

```
template<char... Bits>
cmat qpp::literals::operator"" _prj ( )
```

Multi-partite qubit projector user-defined literal.

See also

qpp::mprj()

Constructs the multi-partite qubit projector $|\mathrm{Bits}\rangle\langle\mathrm{Bits}|$ (in the computational basis)

Template Parameters

Bits String of binary numbers representing the qubit state to project on

\mathbf{L}	ΔT	 rn	c

Multi-partite qubit projector, as a complex dynamic matrix

Chapter 7

Class Documentation

7.1 qpp::Bit_circuit Class Reference


Classical reversible circuit simulator.

#include <classes/reversible.h>

Inheritance diagram for qpp::Bit_circuit:



Collaboration diagram for qpp::Bit_circuit:



Public Member Functions

• Bit_circuit (idx n)

Constructs a bit circuit instance.

• Bit_circuit (const Dynamic_bitset &dynamic_bitset)

Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.

Bit_circuit & X (idx i)

Bit flip.

virtual ∼Bit_circuit ()=default

Default virtual destructor.

• Bit_circuit & NOT (idx i)

Bit flip.

Bit_circuit & CNOT (idx ctrl, idx target)

Controlled-NOT.

• Bit_circuit & TOF (idx i, idx j, idx k)

Toffoli gate.

• Bit_circuit & SWAP (idx i, idx j)

Swap bits.

• Bit_circuit & FRED (idx i, idx j, idx k)

Fredkin gate (Controlled-SWAP)

Bit_circuit & reset () noexcept

Reset the circuit all zero, clear all gates.

- idx get_gate_count (const std::string &name={}) const Bit circuit gate count.
- idx get_gate_depth (const std::string &name={}) const

Bit circuit gate depth.

Private Attributes

- std::unordered_map< std::string, idx > depth_ {}
 gate depths
- Dynamic_bitset bNOT_
- Dynamic_bitset bCNOT_
- Dynamic_bitset bSWAP_
- Dynamic_bitset bTOF_
- Dynamic_bitset bFRED_
- Dynamic_bitset btotal_

used for depth calculations

Additional Inherited Members

7.1.1 Detailed Description

Classical reversible circuit simulator.

7.1.2 Constructor & Destructor Documentation

```
7.1.2.1 Bit_circuit() [1/2]

qpp::Bit_circuit::Bit_circuit (
        idx n ) [inline], [explicit]
```

Constructs a bit circuit instance.

Parameters

n Number of classical bits

Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.

Parameters

```
dynamic_bitset Dynamic bitset
```

```
7.1.2.3 ∼Bit_circuit()
```

```
virtual qpp::Bit_circuit::~Bit_circuit ( ) [virtual], [default]
```

Default virtual destructor.

7.1.3 Member Function Documentation

7.1.3.1 CNOT()

Controlled-NOT.

Parameters

ctrl	Control bit index
target	Target bit index

Returns

Reference to the current instance

7.1.3.2 FRED()

```
Bit_circuit& qpp::Bit_circuit::FRED (
    idx i,
    idx j,
    idx k) [inline]
```

Fredkin gate (Controlled-SWAP)

Parameters

i	Control bit index	
j	Target first bit index	
k	Target second bit index	

Returns

Reference to the current instance

7.1.3.3 get_gate_count()

Bit circuit gate count.

Note

If name is empty (default), returns the total gate count of the circuit

Parameters

name	Gate name (optional). Possible names are NOT (X), CNOT, SWAP, TOF, FRED.
------	--

Returns

Gate count

7.1.3.4 get_gate_depth()

Bit circuit gate depth.

Note

If name is empty (default), returns the total gate depth of the circuit

Parameters

name	Gate name (optional). Possible names are NOT (X), CNOT, SWAP, TOF, FRED.

```
Returns
```

Gate depth

```
7.1.3.5 NOT()
```

```
Bit_circuit& qpp::Bit_circuit::NOT (
        idx i ) [inline]
```

Bit flip.

See also

```
qpp::Bit_circuit::X()
```

Parameters

```
i Bit position in the circuit
```

Returns

Reference to the current instance

```
7.1.3.6 reset()
```

```
Bit_circuit& qpp::Bit_circuit::reset ( ) [inline], [noexcept]
```

Reset the circuit all zero, clear all gates.

Returns

Reference to the current instance

7.1.3.7 SWAP()

```
Bit_circuit& qpp::Bit_circuit::SWAP (
        idx i,
        idx j) [inline]
```

Swap bits.

Parameters

i	Bit index
j	Bit index

Returns

Reference to the current instance

7.1.3.8 TOF()

```
Bit_circuit& qpp::Bit_circuit::TOF (
    idx i,
    idx j,
    idx k) [inline]
```

Toffoli gate.

Parameters

i	Control first bit index
j	Control second bit index
k	Target bit index

Returns

Reference to the current instance

7.1.3.9 X()

```
Bit_circuit@ qpp::Bit_circuit::X (
        idx i ) [inline]
```

Bit flip.

See also

```
qpp::Bit_circuit::NOT()
```

Parameters

i Bit position in the circuit

Returns

Reference to the current instance

7.1.4 Member Data Documentation

```
7.1.4.1 bCNOT_
Dynamic_bitset qpp::Bit_circuit::bCNOT_ [private]
7.1.4.2 bFRED_
Dynamic_bitset qpp::Bit_circuit::bFRED_ [private]
7.1.4.3 bNOT_
Dynamic_bitset qpp::Bit_circuit::bNOT_ [private]
7.1.4.4 bSWAP_
Dynamic_bitset qpp::Bit_circuit::bSWAP_ [private]
7.1.4.5 bTOF_
Dynamic_bitset qpp::Bit_circuit::bTOF_ [private]
7.1.4.6 btotal_
Dynamic_bitset qpp::Bit_circuit::btotal_ [private]
used for depth calculations
```

```
7.1.4.7 count_
```

```
std::unordered_map<std::string, idx> qpp::Bit_circuit::count_ {} [private]
gate counts
```

7.1.4.8 depth_

```
std::unordered_map<std::string, idx> qpp::Bit_circuit::depth_ {} [private]
gate depths
```

The documentation for this class was generated from the following file:


· classes/reversible.h

7.2 qpp::Codes Class Reference


const Singleton class that defines quantum error correcting codes

```
#include <classes/codes.h>
```

Inheritance diagram for qpp::Codes:



Collaboration diagram for qpp::Codes:



Public Types

enum Type { Type::FIVE_QUBIT, Type::SEVEN_QUBIT_STEANE, Type::NINE_QUBIT_SHOR }
 Code types, add more codes here if needed.

Public Member Functions

ket codeword (Type type, idx i) const
 Returns the codeword of the specified code type.

Private Member Functions

• Codes ()

Default constructor.

∼Codes ()=default

Default destructor.

Friends

class internal::Singleton < const Codes >

Additional Inherited Members

7.2.1 Detailed Description

const Singleton class that defines quantum error correcting codes

7.2.2 Member Enumeration Documentation

7.2.2.1 Type

```
enum qpp::Codes::Type [strong]
```

Code types, add more codes here if needed.

See also

qpp::Codes::codeword()

Enumerator

FIVE_QUBIT	[[5,1,3]] qubit code
SEVEN_QUBIT_STEANE	[[7,1,3]] Steane qubit code
NINE_QUBIT_SHOR	[[9,1,3]] Shor qubit code

7.2.3 Constructor & Destructor Documentation

7.2.3.1 Codes()

```
qpp::Codes::Codes ( ) [inline], [private]
```

Default constructor.

7.2.3.2 ∼Codes()

```
qpp::Codes::~Codes ( ) [private], [default]
```

Default destructor.

7.2.4 Member Function Documentation

7.2.4.1 codeword()

Returns the codeword of the specified code type.

See also

```
qpp::Codes::Type
```

Parameters

type	Code type
i	Codeword index

Returns

i-th codeword of the code type

7.2.5 Friends And Related Function Documentation

7.2.5.1 internal::Singleton < const Codes >

```
friend class internal::Singleton< const Codes > [friend]
```

The documentation for this class was generated from the following file:


· classes/codes.h

7.3 qpp::exception::CustomException Class Reference

Custom exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::CustomException:



Collaboration diagram for qpp::exception::CustomException:



Public Member Functions

• CustomException (const std::string &where, const std::string &what)

Private Member Functions

• std::string description () const override Exception description.

Private Attributes

std::string what_{{}}

7.3.1 Detailed Description

Custom exception.

Custom exception, the user must provide a custom message

7.3.2 Constructor & Destructor Documentation

7.3.2.1 CustomException()

7.3.3 Member Function Documentation

7.3.3.1 description()

```
std::string qpp::exception::CustomException::description ( ) const [inline], [override],
[private], [virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.3.4 Member Data Documentation

7.3.4.1 what_

```
std::string qpp::exception::CustomException::what_ {} [private]
```

The documentation for this class was generated from the following file:


classes/exception.h

7.4 qpp::exception::DimsInvalid Class Reference

Invalid dimension(s) exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsInvalid:



Collaboration diagram for qpp::exception::DimsInvalid:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.4.1 Detailed Description

Invalid dimension(s) exception.

std::vector<idx> of dimensions has zero size or contains zeros

7.4.2 Member Function Documentation

7.4.2.1 description()

std::string qpp::exception::DimsInvalid::description () const [inline], [override], [virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.4.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

The documentation for this class was generated from the following file:

· classes/exception.h

7.5 qpp::exception::DimsMismatchCvector Class Reference


Dimension(s) mismatch column vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchCvector:



Collaboration diagram for qpp::exception::DimsMismatchCvector:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.5.1 Detailed Description

Dimension(s) mismatch column vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a column vector)

7.5.2 Member Function Documentation

7.5.2.1 description()

std::string qpp::exception::DimsMismatchCvector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.5.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
WITCIC	Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.6 qpp::exception::DimsMismatchMatrix Class Reference


Dimension(s) mismatch matrix size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchMatrix:



Collaboration diagram for qpp::exception::DimsMismatchMatrix:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.6.1 Detailed Description

Dimension(s) mismatch matrix size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of rows of the Eigen::Matrix (assumed to be a square matrix)

7.6.2 Member Function Documentation

7.6.2.1 description()

```
std::string qpp::exception::DimsMismatchMatrix::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.6.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.7 qpp::exception::DimsMismatchRvector Class Reference


Dimension(s) mismatch row vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchRvector:



Collaboration diagram for qpp::exception::DimsMismatchRvector:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.7.1 Detailed Description

Dimension(s) mismatch row vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row vector)

7.7.2 Member Function Documentation

7.7.2.1 description()

std::string qpp::exception::DimsMismatchRvector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.7.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.8 qpp::exception::DimsMismatchVector Class Reference


Dimension(s) mismatch vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchVector:



Collaboration diagram for qpp::exception::DimsMismatchVector:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.8.1 Detailed Description

Dimension(s) mismatch vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row/column vector)

7.8.2 Member Function Documentation

7.8.2.1 description()

```
std::string qpp::exception::DimsMismatchVector::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.8.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


classes/exception.h

7.9 qpp::exception::DimsNotEqual Class Reference


Dimensions not equal exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsNotEqual:



Collaboration diagram for qpp::exception::DimsNotEqual:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.9.1 Detailed Description

Dimensions not equal exception.

Local/global dimensions are not equal

7.9.2 Member Function Documentation

7.9.2.1 description()

std::string qpp::exception::DimsNotEqual::description () const [inline], [override], [virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.9.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred


The documentation for this class was generated from the following file:

· classes/exception.h

7.10 qpp::internal::Display_Impl_ Struct Reference

```
#include <internal/util.h>
```

Inheritance diagram for qpp::internal::Display_Impl_:



Public Member Functions

template<typename T >
 std::ostream & display_impl_ (const T &A, std::ostream &os, double chop=qpp::chop) const

7.10.1 Member Function Documentation

7.10.1.1 display_impl_()

The documentation for this struct was generated from the following file:


• internal/util.h

7.11 qpp::exception::Duplicates Class Reference


System (e.g. std::vector) has duplicates exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Duplicates:



Collaboration diagram for qpp::exception::Duplicates:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.11.1 Detailed Description

System (e.g. std::vector) has duplicates exception.

7.11.2 Member Function Documentation

7.11.2.1 description()

```
std::string qpp::exception::Duplicates::description ( ) const [inline], [override], [virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.11.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.12 qpp::Dynamic_bitset Class Reference


Dynamic bitset class, allows the specification of the number of bits at runtime.

#include <classes/reversible.h>

Inheritance diagram for qpp::Dynamic_bitset:



Collaboration diagram for qpp::Dynamic_bitset:



Public Types

- using value_type = unsigned int type of the storage elements
- using storage_type = std::vector< value_type > type of the storage

Public Member Functions

• Dynamic_bitset (idx n)

Constructor, initializes all bits to false (zero)

virtual ~Dynamic_bitset ()=default

Default virtual destructor.

const storage_type & data () const

Raw storage space of the bitset.

idx size () const noexcept

Number of bits stored in the bitset.

• idx storage_size () const noexcept

Size of the underlying storage space (in units of value_type, unsigned int by default)

· idx count () const noexcept

Number of bits set to one in the bitset (Hamming weight)

· bool get (idx pos) const noexcept

The value of the bit at position pos.

• bool none () const noexcept

Checks whether none of the bits are set.

• bool all () const noexcept

Checks whether all bits are set.

· bool any () const noexcept

Checks whether any bit is set.

Dynamic_bitset & set (idx pos, bool value=true)

Sets the bit at position pos.

• Dynamic_bitset & set () noexcept

Set all bits to true.

Dynamic_bitset & rand (idx pos, double p=0.5)

Sets the bit at position pos according to a Bernoulli(p) distribution.

Dynamic_bitset & rand (double p=0.5)

Sets all bits according to a Bernoulli(p) distribution.

• Dynamic_bitset & reset (idx pos)

Sets the bit at position pos to false.

• Dynamic_bitset & reset () noexcept

Sets all bits to false.

• Dynamic_bitset & flip (idx pos)

Flips the bit at position pos.

Dynamic_bitset & flip () noexcept

Flips all bits.

bool operator== (const Dynamic_bitset &rhs) const noexcept

Equality operator.

bool operator!= (const Dynamic_bitset &rhs) const noexcept

Inequality operator.

idx operator- (const Dynamic_bitset &rhs) const noexcept

Number of places the two bitsets differ (Hamming distance)

template < class CharT = char, class Traits = std::char_traits < CharT>, class Allocator = std::allocator < CharT>> std::basic_string < CharT, Traits, Allocator > to_string (CharT zero=CharT('0'), CharT one=CharT('1')) const String representation.

Protected Member Functions

• idx index_ (idx pos) const

Index of the pos bit in the storage space.

idx offset_ (idx pos) const

Offset of the pos bit in the storage space relative to its index.

Protected Attributes

```
    idx storage_size_
        storage size
    idx n_
        number of bits
    std::vector < value_type > v_
        storage space
```

Private Member Functions

7.12.1 Detailed Description

Dynamic bitset class, allows the specification of the number of bits at runtime.

Note

The interface mimics std::bitset<>

7.12.2 Member Typedef Documentation

```
7.12.2.1 storage_type
using qpp::Dynamic_bitset::storage_type = std::vector<value_type>
type of the storage

7.12.2.2 value_type
using qpp::Dynamic_bitset::value_type = unsigned int
type of the storage elements
```

7.12.3 Constructor & Destructor Documentation

```
7.12.3.1 Dynamic_bitset()
```

```
qpp::Dynamic_bitset::Dynamic_bitset (
          idx n ) [inline], [explicit]
```

Constructor, initializes all bits to false (zero)

Parameters

n Number of bits in the bitset

```
7.12.3.2 ~Dynamic_bitset()
```

```
virtual qpp::Dynamic_bitset::~Dynamic_bitset ( ) [virtual], [default]
```

Default virtual destructor.

7.12.4 Member Function Documentation

```
7.12.4.1 all()
```

```
bool qpp::Dynamic_bitset::all ( ) const [inline], [noexcept]
```

Checks whether all bits are set.

Returns

True if all of the bits are set

7.12.4.2 any()

```
bool qpp::Dynamic_bitset::any ( ) const [inline], [noexcept]
```

Checks whether any bit is set.

Returns

True if any of the bits is set

7.12.4.3 count()

```
idx qpp::Dynamic_bitset::count ( ) const [inline], [noexcept]
```

Number of bits set to one in the bitset (Hamming weight)

Returns

Hamming weight

7.12.4.4 data()

```
const storage_type& qpp::Dynamic_bitset::data ( ) const [inline]
```

Raw storage space of the bitset.

Returns

Const reference to the underlying storage space

7.12.4.5 display()

qpp::IDisplay::display() override, displays the bitset bit by bit

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.12.4.6 flip() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip (
        idx pos ) [inline]
```

Flips the bit at position pos.

Parameters

pos Position in the bitset

Returns

Reference to the current instance

```
7.12.4.7 flip() [2/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip ( ) [inline], [noexcept]
```

Flips all bits.

Returns

Reference to the current instance

7.12.4.8 get()

```
bool qpp::Dynamic_bitset::get (
          idx pos ) const [inline], [noexcept]
```

The value of the bit at position pos.

Parameters

pos Position in the bitset

Returns

The value of the bit at position pos

7.12.4.9 index_()

Index of the pos bit in the storage space.

Parameters

```
pos Bit location
```

Returns

Index of the pos bit in the storage space

7.12.4.10 none()

```
bool qpp::Dynamic_bitset::none ( ) const [inline], [noexcept]
```

Checks whether none of the bits are set.

Returns

True if none of the bits are set

7.12.4.11 offset_()

Offset of the pos bit in the storage space relative to its index.

Parameters

```
pos Bit location
```

Returns

Offset of the pos bit in the storage space relative to its index

7.12.4.12 operator"!=()

Inequality operator.

Parameters

```
rhs Dynamic_bitset against which the inequality is being tested
```

Returns

True if the bitsets are not equal (bit by bit), false otherwise

7.12.4.13 operator-()

Number of places the two bitsets differ (Hamming distance)

Parameters

rhs Dynamic_bitset against which the Hamming distance is computed

Returns

Hamming distance

7.12.4.14 operator==()

Equality operator.

Parameters

```
rhs Dynamic_bitset against which the equality is being tested
```

Returns

True if the bitsets are equal (bit by bit), false otherwise

7.12.4.15 rand() [1/2]

```
Dynamic_bitset& qpp::Dynamic_bitset::rand (
    idx pos,
    double p = 0.5 ) [inline]
```

Sets the bit at position *pos* according to a Bernoulli(p) distribution.

Parameters

pos	Position in the bitset
р	Probability

Returns

Reference to the current instance

Sets all bits according to a Bernoulli(p) distribution.

Parameters

```
p Probability
```

Returns

Reference to the current instance

Sets the bit at position pos to false.

Parameters

pos Position in the bitset	
----------------------------	--

Returns

Reference to the current instance

```
7.12.4.18 reset() [2/2]
Dynamic_bitset& qpp::Dynamic_bitset::reset ( ) [inline], [noexcept]
Sets all bits to false.
```

Returns

Reference to the current instance

```
7.12.4.19 set() [1/2]
```

Sets the bit at position pos.

Parameters

pos	Position in the bitset
value	Bit value

Returns

Reference to the current instance

```
7.12.4.20 set() [2/2]

Dynamic_bitset& qpp::Dynamic_bitset::set () [inline], [noexcept]
```

Set all bits to true.

Returns

Reference to the current instance

```
7.12.4.21 size()
```

```
idx qpp::Dynamic_bitset::size ( ) const [inline], [noexcept]
```

Number of bits stored in the bitset.

Returns

Number of bits stored in the bitset

```
7.12.4.22 storage_size()
```

```
idx qpp::Dynamic_bitset::storage_size ( ) const [inline], [noexcept]
```

Size of the underlying storage space (in units of value_type, unsigned int by default)

Returns

Size of the underlying storage space

7.12.4.23 to_string()

String representation.

Template Parameters

CharT	String character type
Traits	String traits
Allocator	String Allocator

Parameters

	Character representing the zero
one	Character representing the one

Returns

The bitset as a string

7.12.5 Member Data Documentation

```
7.12.5.1 n_
idx qpp::Dynamic_bitset::n_ [protected]
```

7.12.5.2 storage_size_

number of bits

```
idx qpp::Dynamic_bitset::storage_size_ [protected]
```

storage size

```
7.12.5.3 v_
std::vector<value_type> qpp::Dynamic_bitset::v_ [protected]
storage space
```

The documentation for this class was generated from the following file:

· classes/reversible.h

7.13 qpp::internal::EqualEigen Class Reference

Functor for comparing Eigen expressions for equality.

```
#include <functions.h>
```

Public Member Functions

template<typename Derived >
 bool operator() (const Eigen::MatrixBase< Derived > &A, const Eigen::MatrixBase< Derived > &B) const

7.13.1 Detailed Description

Functor for comparing Eigen expressions for equality.

Note

Works without assertion fails even if the dimensions of the arguments are different (in which case simply returns false

7.13.2 Member Function Documentation

7.13.2.1 operator()()

The documentation for this class was generated from the following file:


· functions.h

7.14 qpp::exception::Exception Class Reference


Base class for generating Quantum++ custom exceptions.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Exception:



Collaboration diagram for qpp::exception::Exception:



Public Member Functions

- Exception (const std::string &where)
 - Constructs an exception.
- const char * what () const noexcept override
 - Overrides std::exception::what()
- virtual std::string description () const =0
 - Exception description.

Private Attributes

- std::string where_
- std::string msg_

7.14.1 Detailed Description

Base class for generating Quantum++ custom exceptions.

Derive from this class if more exceptions are needed, making sure to override qpp::exception::Exception::Exception::description() in the derived class and to inherit the constructor qpp::exception::Exception::Exception(). Preferably keep your newly defined exception classes in the namespace qpp::exception.

Example:

```
namespace qpp
{
namespace exception
{
    class ZeroSize : public Exception
    {
        public:
            std::string description() const override
            {
                  return "Object has zero size";
            }
            // inherit the base class' qpp::exception::Exception constructor
            using Exception::Exception;
        };
} // namespace exception
} // namespace qpp
```

7.14.2 Constructor & Destructor Documentation

7.14.2.1 Exception()

Constructs an exception.

Parameters

where Text representing where the exception occurred

qpp::exception::ZeroSize, and qpp::exception::Unknown.

7.14.3 Member Function Documentation

7.14.3.1 description()

```
std::string qpp::exception::Exception::description ( ) const [inline], [pure virtual]
Exception description.
```

Returns

Exception description

Implemented in qpp::exception::InvalidIterator, qpp::exception::NotImplemented, qpp::exception::CustomException, qpp::exception::Duplicates, qpp::exception::QuditAlreadyMeasured, qpp::exception::UndefinedType, qpp::exception::SizeMismatch, qpp::exception::TypeMismatch, qpp::exception::OutOfRange, qpp::exception::NotOdeword, qpp::exception::NotBipartite, qpp::exception::NotQubitSubsys, qpp::exception::NotQubitVector, qpp::exception::NotQubitRvector, qpp::exception::NotQubitCvector qpp::exception::NotQubitMatrix, qpp::exception::PermMismatchDims, qpp::exception::PermInvalid, qpp::exception::SubsysMismatchEqpp::exception::DimsMismatchVector, qpp::exception::DimsMismatchCvector, qpp::exception::DimsMismatchMatrix, qpp::exception::DimsNotEqual, qpp::exception::DimsInvalid, qpp::exception::MatrixMismatchSupp::exception::MatrixNotSquareNorVector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::MatrixNotSquareNo

7.14.3.2 what()

```
const char* qpp::exception::Exception::what ( ) const [inline], [override], [noexcept]
```

Overrides std::exception::what()

Returns

Exception description

7.14.4 Member Data Documentation

7.14.4.1 msg_

```
std::string qpp::exception::Exception::msg_ [mutable], [private]
```

7.14.4.2 where_

```
std::string qpp::exception::Exception::where_ [private]
```

The documentation for this class was generated from the following file:


· classes/exception.h

7.15 qpp::Gates Class Reference


const Singleton class that implements most commonly used gates

```
#include <classes/gates.h>
```

Inheritance diagram for qpp::Gates:



Collaboration diagram for qpp::Gates:



Public Member Functions

cmat Rn (double theta, const std::vector< double > &n) const

Qubit rotation of theta about the 3-dimensional real (unit) vector n. cmat RX (double theta) const

Qubit rotation of theta about the X axis.

· cmat RY (double theta) const

Qubit rotation of theta about the Y axis.

cmat RZ (double theta) const

Qubit rotation of theta about the Z axis.

• cmat Zd (idx D=2) const

Generalized Z gate for qudits.

cmat SWAPd (idx D=2) const

SWAP gate for qudits.

cmat Fd (idx D=2) const

Quantum Fourier transform gate for qudits.

cmat MODMUL (idx a, idx N, idx n) const

Modular multiplication gate for qubits Implements $|x\rangle \longrightarrow |ax \bmod N\rangle$.

• cmat Xd (idx D=2) const

Generalized X gate for qudits.

• template<typename Derived = Eigen::MatrixXcd>

Derived Id (idx D=2) const

Identity gate.

template<typename Derived >

dyn_mat< typename Derived::Scalar > CTRL (const Eigen::MatrixBase< Derived > &A, const std::vector idx > &ctrl, const std::vector < idx > &target, idx n, idx d=2) const

Generates the multi-partite multiple-controlled-A gate in matrix form.

template<typename Derived >

dyn mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const std::vector< idx > &dims) const

Expands out.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const std::initializer list< idx > &dims) const

Expands out.

```
• template<typename Derived >
       dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, idx n,
       idx d=2) const
          Expands out.

    std::string get_name (const cmat &U) const

          Get the name of the most common qubit gates.
Public Attributes
    • cmat Id2 {cmat::Identity(2, 2)}
          Identity gate.

    cmat H {cmat::Zero(2, 2)}

          Hadamard gate.

    cmat X {cmat::Zero(2, 2)}

          Pauli Sigma-X gate.

    cmat Y {cmat::Zero(2, 2)}

          Pauli Sigma-Y gate.

    cmat Z {cmat::Zero(2, 2)}

          Pauli Sigma-Z gate.

    cmat S {cmat::Zero(2, 2)}

          S gate.
    cmat T {cmat::Zero(2, 2)}
           T gate.

    cmat CNOT {cmat::Identity(4, 4)}

          Controlled-NOT control target gate.

    cmat CZ {cmat::Identity(4, 4)}

          Controlled-Phase gate.
    • cmat CNOTba {cmat::Zero(4, 4)}
          Controlled-NOT target->control gate.
    • cmat SWAP {cmat::Identity(4, 4)}
          SWAP gate.

    cmat TOF {cmat::Identity(8, 8)}

           Toffoli gate.
```

Private Member Functions

Fredkin gate.

• Gates ()

Initializes the gates.

cmat FRED {cmat::Identity(8, 8)}

∼Gates ()=default

Default destructor.

Friends

class internal::Singleton < const Gates >

Additional Inherited Members

7.15.1 Detailed Description

const Singleton class that implements most commonly used gates

7.15.2 Constructor & Destructor Documentation

```
7.15.2.1 Gates()

qpp::Gates::Gates ( ) [inline], [private]

Initializes the gates.

7.15.2.2 ~Gates()

qpp::Gates::~Gates ( ) [private], [default]
```

7.15.3 Member Function Documentation

7.15.3.1 CTRL()

Default destructor.

Generates the multi-partite multiple-controlled-A gate in matrix form.

See also

```
qpp::applyCTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
n	Total number of subsystems
d	Subsystem dimensions

Returns

CTRL-A gate, as a matrix over the same scalar field as A

7.15.3.2 expandout() [1/3]

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

Α	Eigen expression
pos	Position
dims	Dimensions of the multi-partite system

Returns

Tensor product $I \otimes \cdots \otimes I \otimes A \otimes I \otimes \cdots \otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.15.3.3 expandout() [2/3]

Expands out.

See also

```
qpp::kron()
```

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Note

The std::initializer_list overload exists because otherwise, in the degenerate case when *dims* has only one element, the one element list is implicitly converted to the element's underlying type, i.e. qpp::idx, which has the net effect of picking the wrong (non-vector) qpp::expandout() overload

Parameters

Α	Eigen expression
pos	Position
dims	Dimensions of the multi-partite system

Returns

Tensor product $I \otimes \cdots \otimes I \otimes A \otimes I \otimes \cdots \otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.15.3.4 expandout() [3/3]

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

Α	Eigen expression
pos	Position
n	Number of subsystems
d	Subsystem dimensions

Returns

Tensor product $I\otimes\cdots\otimes I\otimes A\otimes I\otimes\cdots\otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.15.3.5 Fd()

```
cmat qpp::Gates::Fd (
    idx D = 2 ) const [inline]
```

Quantum Fourier transform gate for qudits.

Note

```
Defined as F = \sum_{j,k=0}^{D-1} \exp(2\pi \mathrm{i} jk/D) |j\rangle\langle k|
```

Parameters

D Dimension of the Hilbert space

Returns

Fourier transform gate for qudits

7.15.3.6 get_name()

Get the name of the most common qubit gates.

Note

Assumes that the gate U is represented by a square matrix. If not, returns the empty string

Parameters

U | Complex matrix representing the quantum gate

Returns

The name of the gate (if any), otherwise the empty string

7.15.3.7 ld()

```
template<typename Derived = Eigen::MatrixXcd>
Derived qpp::Gates::Id (
    idx D = 2 ) const [inline]
```

Identity gate.

Note

Can change the return type from complex matrix (default) by explicitly specifying the template parameter

Parameters

D Dimension of the Hilbert space

Returns

Identity gate on a Hilbert space of dimension D

7.15.3.8 MODMUL()

```
cmat qpp::Gates::MODMUL (
          idx a,
          idx N,
          idx n ) const [inline]
```

Modular multiplication gate for qubits Implements $|x\rangle \longrightarrow |ax \bmod N\rangle$.

Note

For the gate to be unitary, *a* and *N* should be co-prime. The function does not check co-primality in release versions!

The number of qubits required to implement the gate should satisfy $n \geq \lceil \log_2(N) \rceil$

Parameters

а	Positive integer less than N
N	Positive integer
n	Number of qubits required for implementing the gate

Returns

Modular multiplication gate

7.15.3.9 Rn()

Qubit rotation of *theta* about the 3-dimensional real (unit) vector *n*.

Parameters

theta	Rotation angle
n	3-dimensional real (unit) vector

Returns

Rotation gate

7.15.3.10 RX()

Qubit rotation of theta about the X axis.

Parameters

theta	Rotation angle

Returns

Rotation gate

7.15.3.11 RY()

Qubit rotation of theta about the Y axis.

Parameters

theta	Rotation angle

Returns

Rotation gate

7.15.3.12 RZ()

Qubit rotation of theta about the Z axis.

Parameters

theta	Rotation angle
-------	----------------

Returns

Rotation gate

7.15.3.13 SWAPd()

```
cmat qpp::Gates::SWAPd (
    idx D = 2 ) const [inline]
```

SWAP gate for qudits.

Parameters

D Dimension of the Hilbert space

Returns

SWAP gate for qudits

7.15.3.14 Xd()

```
cmat qpp::Gates::Xd (
        idx D = 2 ) const [inline]
```

Generalized X gate for qudits.

Note

```
Defined as X=\sum_{j=0}^{D-1}|j\oplus 1\rangle\langle j|, i.e. raising operator X|j\rangle=|j\oplus 1\rangle
```

Parameters

D Dimension of the Hilbert space

Returns

Generalized X gate for qudits

7.15.3.15 Zd()

```
cmat qpp::Gates::Zd (
    idx D = 2 ) const [inline]
```

Generalized Z gate for qudits.

Note

Defined as
$$Z = \sum_{j=0}^{D-1} \exp(2\pi \mathrm{i} j/D) |j\rangle\langle j|$$

Parameters

D Dimension of the Hilbert space

Returns

Generalized Z gate for qudits

7.15.4 Friends And Related Function Documentation

7.15.4.1 internal::Singleton < const Gates >

```
friend class internal::Singleton< const Gates > [friend]
```

7.15.5 Member Data Documentation

7.15.5.1 CNOT

```
cmat qpp::Gates::CNOT {cmat::Identity(4, 4)}
```

Controlled-NOT control target gate.

```
7.15.5.2 CNOTba
cmat qpp::Gates::CNOTba {cmat::Zero(4, 4)}
Controlled-NOT target->control gate.
7.15.5.3 CZ
cmat qpp::Gates::CZ {cmat::Identity(4, 4)}
Controlled-Phase gate.
7.15.5.4 FRED
cmat qpp::Gates::FRED {cmat::Identity(8, 8)}
Fredkin gate.
7.15.5.5 H
cmat qpp::Gates::H {cmat::Zero(2, 2)}
Hadamard gate.
7.15.5.6 ld2
cmat qpp::Gates::Id2 {cmat::Identity(2, 2)}
Identity gate.
```

7.15.5.7 S

S gate.

cmat qpp::Gates::S {cmat::Zero(2, 2)}

```
Generated by Doxygen
```

```
7.15.5.8 SWAP
cmat qpp::Gates::SWAP {cmat::Identity(4, 4)}
SWAP gate.
7.15.5.9 T
cmat qpp::Gates::T {cmat::Zero(2, 2)}
T gate.
7.15.5.10 TOF
cmat qpp::Gates::TOF {cmat::Identity(8, 8)}
Toffoli gate.
7.15.5.11 X
cmat qpp::Gates::X {cmat::Zero(2, 2)}
Pauli Sigma-X gate.
7.15.5.12 Y
cmat qpp::Gates::Y {cmat::Zero(2, 2)}
Pauli Sigma-Y gate.
7.15.5.13 Z
cmat qpp::Gates::Z {cmat::Zero(2, 2)}
```

· classes/gates.h

The documentation for this class was generated from the following file:


Pauli Sigma-Z gate.

7.16 qpp::QCircuit::GateStep Struct Reference

One step consisting only of gates/operators in the circuit.

#include <classes/circuits/circuits.h>

Collaboration diagram for qpp::QCircuit::GateStep:



Public Member Functions

• GateStep ()=default

Default constructor.

GateStep (GateType gate_type, std::size_t gate_hash, const std::vector < idx > &ctrl, const std::vector < idx > &trl, const std::vector < idx > &target, std::string name={})

Constructs a gate step instance.

Public Attributes

GateType gate_type_ = GateType::NONE

gate type

std::size_t gate_hash_

gate hash

std::vector< idx > ctrl

control

std::vector< idx > target_

target where the gate is applied

• std::string name_

custom name of the step

7.16.1 Detailed Description

One step consisting only of gates/operators in the circuit.

7.16.2 Constructor & Destructor Documentation

```
7.16.2.1 GateStep() [1/2]

qpp::QCircuit::GateStep::GateStep ( ) [default]
```

Default constructor.

7.16.2.2 GateStep() [2/2]

```
qpp::QCircuit::GateStep::GateStep (
    GateType gate_type,
    std::size_t gate_hash,
    const std::vector< idx > & ctrl,
    const std::vector< idx > & target,
    std::string name = {} ) [inline], [explicit]
```

Constructs a gate step instance.

Parameters

gate_type	Gate type
gate_hash	Hash of the quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes
name	Optional gate name

7.16.3 Member Data Documentation

```
7.16.3.1 ctrl_
std::vector<idx> qpp::QCircuit::GateStep::ctrl_
control
```

```
7.16.3.2 gate_hash_
std::size_t qpp::QCircuit::GateStep::gate_hash_
gate hash
7.16.3.3 gate_type_
GateType qpp::QCircuit::GateStep::gate_type_ = GateType::NONE
gate type
7.16.3.4 name_
std::string qpp::QCircuit::GateStep::name_
custom name of the step
7.16.3.5 target_
std::vector<idx> qpp::QCircuit::GateStep::target_
target where the gate is applied
The documentation for this struct was generated from the following file:
    · classes/circuits/circuits.h
       qpp::internal::HashEigen Class Reference
7.17
```

Functor for hashing Eigen expressions.

```
#include <functions.h>
```

Public Member Functions

template < typename Derived >
 std::size_t operator() (const Eigen::MatrixBase < Derived > &A) const

7.17.1 Detailed Description

Functor for hashing Eigen expressions.

7.17.2 Member Function Documentation

7.17.2.1 operator()()

The documentation for this class was generated from the following file:


· functions.h

7.18 qpp::IDisplay Class Reference

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

```
#include <classes/idisplay.h>
```

Inheritance diagram for qpp::IDisplay:



Public Member Functions

virtual ~IDisplay ()=default
 Default virtual destructor.

Private Member Functions

virtual std::ostream & display (std::ostream &os) const =0
 Must be overridden by all derived classes.

Friends

std::ostream & operator<< (std::ostream &os, const IDisplay &rhs)
 Overloads the extraction operator.

7.18.1 Detailed Description

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

This class defines friend std::ostream& operator<<(std::ostream& os, const qpp::IDisplay& rhs). The latter delegates the work to the pure private virtual function qpp::IDisplay::display() which has to be overridden by all derived classes.

7.18.2 Constructor & Destructor Documentation

```
7.18.2.1 ~IDisplay()

virtual qpp::IDisplay::~IDisplay ( ) [virtual], [default]

Default virtual destructor.
```

7.18.3 Member Function Documentation

```
7.18.3.1 display()
```

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implemented in qpp::QCircuit, qpp::QEngine, qpp::QCircuit::iterator::value_type_, qpp::Dynamic_bitset, qpp::internal::IOManipEigen, qpp::Timer< T, CLOCK_T >, qpp::internal::IOManipPointer< PointerType >, and qpp::internal::IOManipRange< InputIterator >.

7.18.4 Friends And Related Function Documentation

7.18.4.1 operator <<

Overloads the extraction operator.

Delegates the work to the virtual function qpp::IDisplay::display()

The documentation for this class was generated from the following file:


· classes/idisplay.h

7.19 qpp::IJSON Class Reference

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

```
#include <classes/idisplay.h>
```

Inheritance diagram for qpp::IJSON:



Public Member Functions

virtual ∼IJSON ()=default

Default virtual destructor.

virtual std::string to_JSON (bool enclosed_in_curly_brackets=true) const =0
 JSON representation of the derived instance, must be overridden by all derived classes.

7.19.1 Detailed Description

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

7.19.2 Constructor & Destructor Documentation

```
7.19.2.1 \simIJSON() virtual qpp::IJSON::\simIJSON ( ) [virtual], [default]
```

Default virtual destructor.

7.19.3 Member Function Documentation

JSON representation of the derived instance, must be overridden by all derived classes.

Parameters

Implemented in qpp::QCircuit, and qpp::QEngine.

The documentation for this class was generated from the following file:


· classes/idisplay.h

7.20 qpp::Init Class Reference


const Singleton class that performs additional initializations/cleanups

```
#include <classes/init.h>
```

Inheritance diagram for qpp::Init:



Collaboration diagram for qpp::Init:



Private Member Functions

- Init ()
 - Additional initializations.
- ∼Init ()

Cleanups.

Friends

class internal::Singleton < const Init >

Additional Inherited Members

7.20.1 Detailed Description

const Singleton class that performs additional initializations/cleanups

7 20 2	Constructor	& Destructor	Documentation
1.ZU.Z	CONSTRUCTOR	a nesilucioi	Documentation

```
7.20.2.1 Init()

qpp::Init::Init ( ) [inline], [private]
```

Additional initializations.

```
7.20.2.2 ~ Init()

qpp::Init::~Init ( ) [inline], [private]
```

Cleanups.

7.20.3 Friends And Related Function Documentation

```
7.20.3.1 internal::Singleton < const Init >
```

```
friend class internal::Singleton< const Init > [friend]
```

The documentation for this class was generated from the following file:


• classes/init.h

7.21 qpp::exception::InvalidIterator Class Reference


Invalid iterator.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::InvalidIterator:



Collaboration diagram for qpp::exception::InvalidIterator:



Public Member Functions

- std::string description () const override
 - Exception description.
- Exception (const std::string &where)

Constructs an exception.

7.21.1 Detailed Description

Invalid iterator.

7.21.2 Member Function Documentation

7.21.2.1 description()

```
std::string qpp::exception::InvalidIterator::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.21.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--


The documentation for this class was generated from the following file:

• classes/exception.h


7.22 qpp::internal::IOManipEigen Class Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipEigen:



Collaboration diagram for qpp::internal::IOManipEigen:



Public Member Functions

- template<typename Derived > IOManipEigen (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
- IOManipEigen (const cplx z, double chop=qpp::chop)

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- cmat A
- double chop_

7.22.1 Constructor & Destructor Documentation

7.22.2 Member Function Documentation

```
7.22.2.1 display()
```

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.22.3 Member Data Documentation

7.22.3.1 A_

```
cmat qpp::internal::IOManipEigen::A_ [private]
```

7.22.3.2 chop_

double qpp::internal::IOManipEigen::chop_ [private]


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


7.23 qpp::internal::IOManipPointer< PointerType > Class Template Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipPointer< PointerType >:



Collaboration diagram for qpp::internal::IOManipPointer< PointerType >:



Public Member Functions

- IOManipPointer (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")
- IOManipPointer (const IOManipPointer &)=default
- IOManipPointer & operator= (const IOManipPointer &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- const PointerType * p_
- idx N_
- std::string separator_
- std::string start_
- · std::string end_

7.23.1 Constructor & Destructor Documentation

```
7.23.1.1 IOManipPointer() [1/2]
```

7.23.1.2 IOManipPointer() [2/2]

7.23.2 Member Function Documentation

7.23.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.23.2.2 operator=()

7.23.3 Member Data Documentation

```
7.23.3.1 end_
```

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::end_ [private]
```

7.23.3.2 N_

```
template<typename PointerType>
idx qpp::internal::IOManipPointer< PointerType >::N_ [private]
```

7.23.3.3 p_

```
template<typename PointerType>
const PointerType* qpp::internal::IOManipPointer< PointerType >::p_ [private]
```

7.23.3.4 separator_

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::separator_ [private]
```

7.23.3.5 start

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::start_ [private]
```


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


7.24 qpp::internal::IOManipRange < InputIterator > Class Template Reference

#include <internal/classes/iomanip.h>

 $Inheritance\ diagram\ for\ qpp::internal::IOManipRange < InputIterator >:$



Collaboration diagram for qpp::internal::IOManipRange< InputIterator >:



Public Member Functions

- IOManipRange (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")
- IOManipRange (const IOManipRange &)=default
- IOManipRange & operator= (const IOManipRange &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- InputIterator first_
- InputIterator last_
- std::string separator_
- std::string start_
- std::string end_

7.24.1 Constructor & Destructor Documentation

7.24.1.1 | IOManipRange() [1/2]

7.24.1.2 IOManipRange() [2/2]

7.24.2 Member Function Documentation

7.24.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.24.2.2 operator=()

7.24.3 Member Data Documentation

```
7.24.3.1 end_
```

```
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::end_ [private]
```

7.24.3.2 first_

```
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::first_ [private]
```

7.24.3.3 last_

```
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::last_ [private]
```

7.24.3.4 separator_

```
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::separator_ [private]
```

7.24.3.5 start_

```
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::start_ [private]
```

The documentation for this class was generated from the following file:


• internal/classes/iomanip.h

7.25 qpp::is_complex< T > Struct Template Reference


Checks whether the type is a complex type.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_complex< T >:



Collaboration diagram for qpp::is_complex< T >:



7.25.1 Detailed Description

template < typename T > struct qpp::is_complex < T >

Checks whether the type is a complex type.

Provides the constant member *value* which is equal to *true*, if the type is a complex type, i.e. *std::complex<T>*

The documentation for this struct was generated from the following file:


traits.h

7.26 qpp::is_complex < std::complex < T > > Struct Template Reference


Checks whether the type is a complex number type, specialization for complex types.

#include <traits.h>

Inheritance diagram for qpp::is_complex < std::complex < T > :



Collaboration diagram for qpp::is_complex< std::complex< T > >:



7.26.1 Detailed Description

 $\label{template} \begin{tabular}{ll} template < typename T > \\ struct qpp::is_complex < std::complex < T > > \\ \end{tabular}$

Checks whether the type is a complex number type, specialization for complex types.

The documentation for this struct was generated from the following file:


· traits.h

7.27 qpp::is_iterable < T, typename > Struct Template Reference


Checks whether T is compatible with an STL-like iterable container.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_iterable < T, typename >:



Collaboration diagram for qpp::is_iterable < T, typename >:



7.27.1 Detailed Description

template<typename T, typename = void> struct qpp::is_iterable< T, typename >

Checks whether T is compatible with an STL-like iterable container.

Provides the constant member *value* which is equal to *true*, if *T* is compatible with an iterable container, i.e. provides at least *begin()* and *end()* member functions and allows de-referencing. Otherwise, *value* is equal to *false*.

The documentation for this struct was generated from the following file:


traits.h

7.28 qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().begin())) > Struct Template Reference


Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(*(std::declval < T >().begin())) > :



Collaboration diagram for qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std:: \leftarrow :declval< T >().end()), decltype(*(std::declval< T >().begin()))>>:



7.28.1 Detailed Description

 $template < typename \ T > \\ struct \ qpp::is_iterable < T, \ to_void < \ decltype(std::declval < T > ().begin()), \ decltype(std::declval < T > ().end()), \ decltype(*(std \leftarrow ::declval < T > ().begin())) > \\ \end{cases}$

Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

The documentation for this struct was generated from the following file:

· traits.h

7.29 qpp::is_matrix_expression < Derived > Struct Template Reference


Checks whether the type is an Eigen matrix expression.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_matrix_expression< Derived >:



Collaboration diagram for qpp::is_matrix_expression< Derived >:



7.29.1 Detailed Description

template<typename Derived>
struct qpp::is_matrix_expression< Derived >

Checks whether the type is an Eigen matrix expression.

Provides the constant member *value* which is equal to *true*, if the type is an Eigen matrix expression of type *Eigen ∷MatrixBase Oerived >*. Otherwise, *value* is equal to *false*.

The documentation for this struct was generated from the following file:


· traits.h

7.30 qpp::QCircuit::iterator Class Reference

Quantum circuit bound-checking (safe) iterator.

#include <classes/circuits/circuits.h>

Collaboration diagram for qpp::QCircuit::iterator:



Classes

· class value_type_

Value type class for qpp::QCircuit::iterator.

Public Types

• using difference_type = long long

iterator trait

• using value_type = value_type_

iterator trait

using pointer = const value_type *

iterator trait

• using reference = const value_type &

iterator trait

using iterator_category = std::forward_iterator_tag

iterator trait

Public Member Functions

• iterator ()=default

Default constructor.

• iterator (const iterator &)=default

Default copy constructor.

• iterator & operator= (const iterator &)=default

Default copy assignment operator.

iterator & operator++ ()

Prefix increment operator.

iterator operator++ (int)

Postfix increment operator.

```
    bool operator== (const iterator &rhs) const
Equality operator.
```

• bool operator!= (iterator rhs) const

Inequality operator.

• const value_type_ & operator* () const

Safe de-referencing operator.

void set_begin_ (const QCircuit *qc)

Sets the iterator to std::begin(this)

void set_end_ (const QCircuit *qc)

Sets the iterator to std::begin(this)

Private Attributes

```
const QCircuit * qc_ {nullptr}
```

< non-owning pointer to the parent const quantum circuit

value_type_ elem_ {nullptr}

7.30.1 Detailed Description

Quantum circuit bound-checking (safe) iterator.

Note

The iterator is a const_iterator by default

7.30.2 Member Typedef Documentation

```
7.30.2.1 difference_type
```

```
using qpp::QCircuit::iterator::difference_type = long long
```

iterator trait

7.30.2.2 iterator_category

```
using qpp::QCircuit::iterator::iterator_category = std::forward_iterator_tag
```

iterator trait

```
7.30.2.3 pointer

using qpp::QCircuit::iterator::pointer = const value_type*
iterator trait

7.30.2.4 reference

using qpp::QCircuit::iterator::reference = const value_type&
iterator trait

7.30.2.5 value_type

using qpp::QCircuit::iterator::value_type = value_type_
iterator trait
```

7.30.3 Constructor & Destructor Documentation

7.30.4 Member Function Documentation

Default copy constructor.

Parameters

rhs Iterator against which the inequality is being tested

Returns

True if the iterators are not equal (bit by bit), false otherwise

```
7.30.4.2 operator*()
```

```
const value_type_& qpp::QCircuit::iterator::operator* ( ) const [inline]
```

Safe de-referencing operator.

Returns

Constant reference to the iterator element

```
7.30.4.3 operator++() [1/2]
```

```
iterator& qpp::QCircuit::iterator::operator++ ( ) [inline]
```

Prefix increment operator.

Returns

Reference to the current instance

```
7.30.4.4 operator++() [2/2]
```

Postfix increment operator.

Returns

Copy of the current instance before the increment

```
7.30.4.5 operator=()
```

Default copy assignment operator.

Returns

Reference to the current instance

```
7.30.4.6 operator==()
```

Equality operator.

Parameters

rhs | Iterator against which the equality is being tested

Returns

True if the iterators are equal, false otherwise

```
7.30.4.7 set_begin_()
```

Sets the iterator to std::begin(this)

Parameters

qc | Pointer to constant quantum circuit

```
7.30.4.8 set_end_()
```

Sets the iterator to std::begin(this)

Parameters

qc Pointer to constant quantum circuit

7.30.5 Member Data Documentation

```
7.30.5.1 elem_
value_type_ qpp::QCircuit::iterator::elem_ {nullptr} [private]

7.30.5.2 qc_
const QCircuit* qpp::QCircuit::iterator::qc_ {nullptr} [private]
< non-owning pointer to the parent const quantum circuit</pre>
```

The documentation for this class was generated from the following file:

• classes/circuits/circuits.h

7.31 qpp::make_void < Ts > Struct Template Reference

Helper for qpp::to_void<> alias template.

```
#include <traits.h>
```

Public Types

• typedef void type

7.31.1 Detailed Description

```
template<typename... Ts>
struct qpp::make_void< Ts>
```

Helper for qpp::to_void<>> alias template.

See also

qpp::to_void<>

7.31.2 Member Typedef Documentation

7.31.2.1 type

```
template<typename... Ts>
typedef void qpp::make_void< Ts >::type
```

The documentation for this struct was generated from the following file:


· traits.h

7.32 qpp::exception::MatrixMismatchSubsys Class Reference


Matrix mismatch subsystems exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::MatrixMismatchSubsys:



Collaboration diagram for qpp::exception::MatrixMismatchSubsys:



Public Member Functions

- std::string description () const override
 - Exception description.
- Exception (const std::string &where)

Constructs an exception.

7.32.1 Detailed Description

Matrix mismatch subsystems exception.

Matrix size mismatch subsystem sizes (e.g. in qpp::apply())

7.32.2 Member Function Documentation

7.32.2.1 description()

std::string qpp::exception::MatrixMismatchSubsys::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.32.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.33 qpp::exception::MatrixNotCvector Class Reference


Matrix is not a column vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotCvector:



Collaboration diagram for qpp::exception::MatrixNotCvector:



Public Member Functions

• std::string description () const override

Exception description.

Exception (const std::string &where)

Constructs an exception.

7.33.1 Detailed Description

Matrix is not a column vector exception.

Eigen::Matrix is not a column vector

7.33.2 Member Function Documentation

7.33.2.1 description()

```
std::string qpp::exception::MatrixNotCvector::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.33.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred	
-------	--	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.34 qpp::exception::MatrixNotRvector Class Reference


Matrix is not a row vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotRvector:



Collaboration diagram for qpp::exception::MatrixNotRvector:



Public Member Functions

• std::string description () const override

Exception description.

Exception (const std::string &where)

Constructs an exception.

7.34.1 Detailed Description

Matrix is not a row vector exception.

Eigen::Matrix is not a row vector

7.34.2 Member Function Documentation

7.34.2.1 description()

```
std::string qpp::exception::MatrixNotRvector::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.34.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred	
-------	--	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.35 qpp::exception::MatrixNotSquare Class Reference


Matrix is not square exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquare:



Collaboration diagram for qpp::exception::MatrixNotSquare:



Public Member Functions

• std::string description () const override

Exception description.

Exception (const std::string &where)

Constructs an exception.

7.35.1 Detailed Description

Matrix is not square exception.

Eigen::Matrix is not a square matrix

7.35.2 Member Function Documentation

7.35.2.1 description()

```
std::string qpp::exception::MatrixNotSquare::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.35.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred	
-------	--	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.36 qpp::exception::MatrixNotSquareNorCvector Class Reference


Matrix is not square nor column vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorCvector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorCvector:



Public Member Functions

• std::string description () const override

Exception description.

Exception (const std::string &where)

Constructs an exception.

7.36.1 Detailed Description

Matrix is not square nor column vector exception.

Eigen::Matrix is not a square matrix nor a column vector

7.36.2 Member Function Documentation

7.36.2.1 description()

std::string qpp::exception::MatrixNotSquareNorCvector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.36.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.37 qpp::exception::MatrixNotSquareNorRvector Class Reference


Matrix is not square nor row vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorRvector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorRvector:



Public Member Functions

• std::string description () const override

Exception description.

Exception (const std::string &where)

Constructs an exception.

7.37.1 Detailed Description

Matrix is not square nor row vector exception.

Eigen::Matrix is not a square matrix nor a row vector

7.37.2 Member Function Documentation

7.37.2.1 description()

std::string qpp::exception::MatrixNotSquareNorRvector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.37.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.38 qpp::exception::MatrixNotSquareNorVector Class Reference


Matrix is not square nor vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorVector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorVector:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.38.1 Detailed Description

Matrix is not square nor vector exception.

Eigen::Matrix is not a square matrix nor a row/column vector

7.38.2 Member Function Documentation

7.38.2.1 description()

std::string qpp::exception::MatrixNotSquareNorVector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.38.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.39 qpp::exception::MatrixNotVector Class Reference


Matrix is not a vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotVector:



Collaboration diagram for qpp::exception::MatrixNotVector:



Public Member Functions

• std::string description () const override

Exception description.

Exception (const std::string &where)

Constructs an exception.

7.39.1 Detailed Description

Matrix is not a vector exception.

Eigen::Matrix is not a row or column vector

7.39.2 Member Function Documentation

7.39.2.1 description()

```
std::string qpp::exception::MatrixNotVector::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.39.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred	
-------	--	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.40 qpp::QCircuit::MeasureStep Struct Reference

One step consisting only of measurements in the circuit.

#include <classes/circuits/circuits.h>

Collaboration diagram for qpp::QCircuit::MeasureStep:



Public Member Functions

• MeasureStep ()=default

Default constructor.

MeasureStep (MeasureType measurement_type, const std::vector< std::size_t > &mats_hash, const std
 ::vector< idx > &target, idx c_reg, std::string name={})

Constructs a measurement step instance.

Public Attributes

MeasureType measurement_type_ = MeasureType::NONE

measurement type

- std::vector< std::size_t > mats_hash_
- std::vector< idx > target_

target where the measurement is applied

- idx c_reg_ {}
- std::string name_

custom name of the step

7.40.1 Detailed Description

One step consisting only of measurements in the circuit.

7.40.2 Constructor & Destructor Documentation

```
7.40.2.1 MeasureStep() [1/2]
```

```
qpp::QCircuit::MeasureStep::MeasureStep ( ) [default]
```

Default constructor.

7.40.2.2 MeasureStep() [2/2]

Constructs a measurement step instance.

Parameters

measurement_type	Measurement type
mats_hash	Vector of hashes of the measurement matrix/matrices
target	Target qudit indexes
c_reg	Classical register where the value of the measurement is stored
name	Optional gate name

7.40.3 Member Data Documentation

```
7.40.3.1 c_reg_
```

```
idx qpp::QCircuit::MeasureStep::c_reg_ {}
```

index of the classical register where the measurement result is being stored

```
7.40.3.2 mats_hash_
```

```
std::vector<std::size_t> qpp::QCircuit::MeasureStep::mats_hash_
```

hashes of measurement matrix/matrices

7.40.3.3 measurement_type_

```
MeasureType qpp::QCircuit::MeasureStep::measurement_type_ = MeasureType::NONE
```

measurement type

7.40.3.4 name_

std::string qpp::QCircuit::MeasureStep::name_

custom name of the step

7.40.3.5 target_

std::vector<idx> qpp::QCircuit::MeasureStep::target_

target where the measurement is applied

The documentation for this struct was generated from the following file:


· classes/circuits/circuits.h

7.41 qpp::exception::NoCodeword Class Reference


Codeword does not exist exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NoCodeword:



Collaboration diagram for qpp::exception::NoCodeword:



Public Member Functions

- std::string description () const override
 - Exception description.
- Exception (const std::string &where)

Constructs an exception.

7.41.1 Detailed Description

Codeword does not exist exception.

Codeword does not exist, thrown when calling qpp::Codes::codeword() with an invalid index

7.41.2 Member Function Documentation

7.41.2.1 description()

std::string qpp::exception::NoCodeword::description () const [inline], [override], [virtual]
Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.41.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.42 qpp::NoiseBase < T > Class Template Reference

Base class for all noise models, derive your particular noise model.

#include <classes/noise.h>

Collaboration diagram for qpp::NoiseBase< T >:



Public Types

• using noise_type = T

Public Member Functions

template<typename U = noise_type>
 NoiseBase (const std::vector< cmat > &Ks, typename std::enable_if< std::is_same< NoiseType::StateDependent,
 U >::value >::type *=nullptr)

Constructs a noise instance for StateDependent noise type.

• template<typename U = noise_type>

NoiseBase (const std::vector< cmat > &Ks, const std::vector< double > &probs, typename std::enable_if< std::is_same< NoiseType::StateIndependent, U >::value >::type *=nullptr)

Constructs a noise instance for StateIndependent noise type.

virtual ∼NoiseBase ()=default

Default virtual destructor.

idx get d () const noexcept

Qudit dimension.

std::vector < cmat > get_Ks () const

Vector of noise operators.

• std::vector< double > get_probs () const

Vector of probabilities corresponding to each noise operator.

idx get_last_idx () const

Index of the last occurring noise element.

double get_last_p () const

Probability of the last occurring noise element.

cmat get_last_K () const

Last occurring noise element.

virtual cmat operator() (const cmat &state) const

Function invocation operator, applies the underlying noise model on the state vector or density matrix state.

· virtual cmat operator() (const cmat &state, idx target) const

Function invocation operator, applies the underlying noise model on qudit target of the multi-partite state vector or density matrix state.

virtual cmat operator() (const cmat &state, const std::vector < idx > &target) const

Function invocation operator, applies the underlying correlated noise model on qudits specified by target of the multipartite state vector or density matrix state.

Protected Member Functions

void compute_probs_ (const cmat &state, const std::vector < idx > &target) const

Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

cmat compute_state_ (const cmat &state, const std::vector< idx > &target) const

Compute the resulting state after the noise was applied.

Protected Attributes

const std::vector< cmat > Ks_

Kraus operators.

std::vector< double > probs

probabilities

idx d_ {}

qudit dimension

idx i_ {}

index of the last occurring noise element

bool generated_ {false}

invoked, or if the noise is state-independent

7.42.1 Detailed Description

```
\label{eq:class} \begin{array}{l} \text{template}{<}\text{class T}{>} \\ \text{class qpp::NoiseBase}{<}\text{T}{>} \end{array}
```

Base class for all noise models, derive your particular noise model.

7.42.2 Member Typedef Documentation

7.42.2.1 noise_type

```
template<class T>
using qpp::NoiseBase< T >::noise_type = T
```

7.42.3 Constructor & Destructor Documentation

7.42.3.1 NoiseBase() [1/2]

Constructs a noise instance for StateDependent noise type.

Note

SFINAEd-out for StateIndependent noise

Parameters

Ks | Vector of noise (Kraus) operators that specify the noise

7.42.3.2 NoiseBase() [2/2]

```
template<class T>
template<typename U = noise_type>
```

Constructs a noise instance for StateIndependent noise type.

Note

SFINAEd-out for StateDependent noise

Parameters

Ks	Vector of noise (Kraus) operators that specify the noise
probs	Vector of probabilities corresponding to each Kraus operator

7.42.3.3 ∼NoiseBase()

```
template<class T>
virtual qpp::NoiseBase< T >::~NoiseBase () [virtual], [default]
```

Default virtual destructor.

7.42.4 Member Function Documentation

7.42.4.1 compute_probs_()

Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

Parameters

state	State vector or density matrix
target	Qudit indexes where the noise is applied

7.42.4.2 compute_state_()

Compute the resulting state after the noise was applied.

Parameters

state	State vector or density matrix
target	Qudit indexes where the noise is applied

Returns

Resulting state after the noise was applied

7.42.4.3 get_d()

```
template<class T>
idx qpp::NoiseBase< T >::get_d ( ) const [inline], [noexcept]
```

Qudit dimension.

Returns

Qudit dimension

7.42.4.4 get_Ks()

```
template<class T>
std::vector<cmat> qpp::NoiseBase< T >::get_Ks () const [inline]
```

Vector of noise operators.

Returns

Vector of noise operators

```
7.42.4.5 get_last_idx()
```

```
template<class T>
idx qpp::NoiseBase< T >::get_last_idx ( ) const [inline]
```

Index of the last occurring noise element.

Returns

Index of the last occurring noise element

7.42.4.6 get_last_K()

```
template<class T>
cmat qpp::NoiseBase< T >::get_last_K ( ) const [inline]
```

Last occurring noise element.

Returns

Last occurring noise element

7.42.4.7 get_last_p()

```
template<class T>
double qpp::NoiseBase< T >::get_last_p ( ) const [inline]
```

Probability of the last occurring noise element.

Returns

Probability of the last occurring noise element

7.42.4.8 get_probs()

```
template < class T >
std::vector < double > qpp::NoiseBase < T >::get_probs ( ) const [inline]
```

Vector of probabilities corresponding to each noise operator.

Returns

Probability vector

7.42.4.9 operator()() [1/3]

Function invocation operator, applies the underlying noise model on the state vector or density matrix state.

Parameters

State vector or density matrix	state
--------------------------------	-------

Returns

Resulting state vector or density matrix

Function invocation operator, applies the underlying noise model on qudit *target* of the multi-partite state vector or density matrix *state*.

Parameters

state	Multi-partite state vector or density matrix
target	Qudit index where the noise is applied

Returns

Resulting state vector or density matrix

Function invocation operator, applies the underlying correlated noise model on qudits specified by *target* of the multi-partite state vector or density matrix *state*.

const std::vector< idx > & target) const [inline], [virtual]

Parameters

state	Multi-partite state vector or density matrix
target	Qudit indexes where the correlated noise is applied

Returns

Resulting state vector or density matrix

7.42.5 Member Data Documentation

```
7.42.5.1 d_
template<class T>
idx qpp::NoiseBase< T >::d_ {} [mutable], [protected]
qudit dimension
7.42.5.2 generated
template<class T>
bool qpp::NoiseBase< T >::generated_ {false} [mutable], [protected]
invoked, or if the noise is state-independent
set to true after compute_state_() is
7.42.5.3 i_
template<class T>
idx qpp::NoiseBase< T >::i_ {} [mutable], [protected]
index of the last occurring noise element
```

```
7.42.5.4 Ks_
```

```
template<class T>
const std::vector<cmat> qpp::NoiseBase< T >::Ks_ [protected]
```

Kraus operators.

7.42.5.5 probs_

```
template < class T>
std::vector < double > qpp::NoiseBase < T >::probs_ [mutable], [protected]
```

probabilities

The documentation for this class was generated from the following file:

· classes/noise.h

7.43 qpp::NoiseType Class Reference

Contains template tags used to specify the noise type.

```
#include <classes/noise.h>
```

Classes

· class StateDependent

Template tag, used whenever the noise is state-dependent.

· class StateIndependent

Template tag, used whenever the noise is state-independent.

7.43.1 Detailed Description

Contains template tags used to specify the noise type.

The documentation for this class was generated from the following file:


• classes/noise.h

7.44 qpp::exception::NotBipartite Class Reference


Not bi-partite exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::NotBipartite:



Collaboration diagram for qpp::exception::NotBipartite:



Public Member Functions

- std::string description () const override Exception description.
- Exception (const std::string &where)

 Constructs an exception.

7.44.1 Detailed Description

Not bi-partite exception.

std::vector<idx> of dimensions has size different from 2

7.44.2 Member Function Documentation

7.44.2.1 description()

```
std::string qpp::exception::NotBipartite::description ( ) const [inline], [override], [virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.44.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.45 qpp::exception::NotImplemented Class Reference


Code not yet implemented.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception::NotImplemented:$



Collaboration diagram for qpp::exception::NotImplemented:



Public Member Functions

- std::string description () const override
 - Exception description.
- Exception (const std::string &where)

Constructs an exception.

7.45.1 Detailed Description

Code not yet implemented.

7.45.2 Member Function Documentation

7.45.2.1 description()

```
std::string qpp::exception::NotImplemented::description ( ) const [inline], [override], [virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.45.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
WIICIC	I TEXT LEDI ESCULUIU MUCIE THE EXCEDITOR OCCURRED

The documentation for this class was generated from the following file:


· classes/exception.h

7.46 qpp::exception::NotQubitCvector Class Reference


Column vector is not 2 x 1 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitCvector:



Collaboration diagram for qpp::exception::NotQubitCvector:



Public Member Functions

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.46.1 Detailed Description

Column vector is not 2 x 1 exception.

Eigen::Matrix is not 2 x 1

7.46.2 Member Function Documentation

7.46.2.1 description()

```
std::string qpp::exception::NotQubitCvector::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.46.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.47 qpp::exception::NotQubitMatrix Class Reference


Matrix is not 2 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitMatrix:



Collaboration diagram for qpp::exception::NotQubitMatrix:



Public Member Functions

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.47.1 Detailed Description

Matrix is not 2 x 2 exception.

Eigen::Matrix is not 2 x 2

7.47.2 Member Function Documentation

7.47.2.1 description()

std::string qpp::exception::NotQubitMatrix::description () const [inline], [override], [virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.47.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.48 qpp::exception::NotQubitRvector Class Reference


Row vector is not 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitRvector:



Collaboration diagram for qpp::exception::NotQubitRvector:



Public Member Functions

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.48.1 Detailed Description

Row vector is not 1 x 2 exception.

Eigen::Matrix is not 1 x 2

7.48.2 Member Function Documentation

7.48.2.1 description()

```
std::string qpp::exception::NotQubitRvector::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.48.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.49 qpp::exception::NotQubitSubsys Class Reference


Subsystems are not qubits exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitSubsys:



Collaboration diagram for qpp::exception::NotQubitSubsys:



Public Member Functions

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.49.1 Detailed Description

Subsystems are not qubits exception.

Subsystems are not 2-dimensional (qubits)

7.49.2 Member Function Documentation

7.49.2.1 description()

std::string qpp::exception::NotQubitSubsys::description () const [inline], [override], [virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.49.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.50 qpp::exception::NotQubitVector Class Reference


Vector is not 2 x 1 nor 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitVector:



Collaboration diagram for qpp::exception::NotQubitVector:



Public Member Functions

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.50.1 Detailed Description

Vector is not 2 x 1 nor 1 x 2 exception.

Eigen::Matrix is not 2 x 1 nor 1 x 2

7.50.2 Member Function Documentation

7.50.2.1 description()

std::string qpp::exception::NotQubitVector::description () const [inline], [override], [virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.50.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

	where	Text representing where the exception occurred	1
--	-------	--	---

The documentation for this class was generated from the following file:


· classes/exception.h

7.51 qpp::exception::OutOfRange Class Reference


Argument out of range exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::OutOfRange:



Collaboration diagram for qpp::exception::OutOfRange:



Public Member Functions

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.51.1 Detailed Description

Argument out of range exception.

Argument out of range

7.51.2 Member Function Documentation

7.51.2.1 description()

```
std::string qpp::exception::OutOfRange::description ( ) const [inline], [override], [virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.51.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the	e exception occurred
-----------------------------------	----------------------

The documentation for this class was generated from the following file:


· classes/exception.h

7.52 qpp::exception::PermInvalid Class Reference


Invalid permutation exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermInvalid:



Collaboration diagram for qpp::exception::PermInvalid:



Public Member Functions

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.52.1 Detailed Description

Invalid permutation exception.

std::vector<idx> does note represent a valid permutation

7.52.2 Member Function Documentation

7.52.2.1 description()

```
std::string qpp::exception::PermInvalid::description ( ) const [inline], [override], [virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.52.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the	e exception occurred
-----------------------------------	----------------------

The documentation for this class was generated from the following file:


· classes/exception.h

7.53 qpp::exception::PermMismatchDims Class Reference


Permutation mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermMismatchDims:



Collaboration diagram for qpp::exception::PermMismatchDims:



Public Member Functions

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.53.1 Detailed Description

Permutation mismatch dimensions exception.

Size of the std::vector<idx> representing the permutation is different from the size of the std::vector<idx> of dimensions

7.53.2 Member Function Documentation

7.53.2.1 description()

```
std::string qpp::exception::PermMismatchDims::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.53.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

The documentation for this class was generated from the following file:


· classes/exception.h

7.54 qpp::QCircuit Class Reference


Quantum circuit class.

#include <classes/circuits/circuits.h>

Inheritance diagram for qpp::QCircuit:



Collaboration diagram for qpp::QCircuit:



Classes

• struct GateStep

One step consisting only of gates/operators in the circuit.

· class iterator

Quantum circuit bound-checking (safe) iterator.

struct MeasureStep

One step consisting only of measurements in the circuit.

Public Types

enum GateType {

GateType::NONE, GateType::SINGLE, GateType::TWO, GateType::THREE,

 ${\tt GateType::CUSTOM, GateType::FAN, GateType::SINGLE_CTRL_SINGLE_TARGET, GateType::SINGLE_CTRL_MULTIPLE_CTRL_SINGLE_CTRL_MULTIPLE_CTRL_SINGLE_CTRL_MULTIPLE_CTRL_SINGLE_CTRL_MULTIPLE_CTRL_SINGLE_CTRL_MULTIPLE_CTRL_SINGLE_CTRL_MULTIPLE_CTRL$

GateType::MULTIPLE CTRL SINGLE TARGET, GateType::MULTIPLE CTRL MULTIPLE TARGET,

GateType::CUSTOM CTRL, GateType::SINGLE cCTRL SINGLE TARGET,

GateType::SINGLE cCTRL MULTIPLE TARGET, GateType::MULTIPLE cCTRL SINGLE TARGET,

GateType::MULTIPLE_cCTRL_MULTIPLE_TARGET, GateType::CUSTOM_cCTRL }

Type of gate being executed in a gate step.

 enum MeasureType { MeasureType::NONE, MeasureType::MEASURE_Z, MeasureType::MEASURE_V, MeasureType::MEASURE V MANY }

Type of measurement being executed in a measurement step.

enum StepType { StepType::NONE, StepType::GATE, StepType::MEASUREMENT, StepType::NOP }

Types of each step in the quantum circuit.

using const iterator = iterator

both iterators are const_iterators

Public Member Functions

· iterator begin ()

Iterator to the first element.

· const iterator begin () const noexcept

Constant iterator to the first element.

const_iterator cbegin () const noexcept

Constant iterator to the first element.

· iterator end ()

Iterator to the next to the last element.

· const_iterator end () const noexcept

Constant iterator to the next to the last element.

· const_iterator cend () const noexcept

Constant iterator to the next to the last element.

QCircuit (idx nq, idx nc=0, idx d=2, std::string name={})

Constructs a quantum circuit.

virtual ~QCircuit ()=default

Default virtual destructor.

idx get_nq () const noexcept

Total number of qudits in the circuit.

• idx get_nc () const noexcept

Total number of classical dits in the circuit.

• idx get_d () const noexcept

Dimension of the comprising qudits.

• std::string get_name () const

Quantum circuit name.

• idx get measured (idx i) const

Check whether qudit i was already measured.

std::vector< idx > get_measured () const

Vector of already measured qudit indexes.

std::vector< idx > get non measured () const

Vector of non-measured qudit indexes.

idx get_gate_count (const std::string &name={}) const

Quantum circuit gate count.

idx get_gate_depth (const std::string &name={}) const

Quantum circuit gate depth.

idx get_measurement_count () const noexcept

Quantum circuit total measurement count.

• idx get_measurement_count (const std::string &name) const

Quantum circuit measurement count.

idx get_step_count () const noexcept

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

• idx get_nop_count () const

No-op count.

QCircuit & gate (const cmat &U, idx i, std::string name={})

Applies the single qudit gate U on single qudit i.

QCircuit & gate (const cmat &U, idx i, idx j, std::string name={})

Applies the two qudit gate U on qudits i and j.

QCircuit & gate (const cmat &U, idx i, idx j, idx k, std::string name={})

Applies the three qudit gate U on qudits i, j and k.

QCircuit & gate fan (const cmat &U, const std::vector < idx > &target, std::string name={})

Applies the single qudit gate U on every qudit listed in target.

• QCircuit & gate fan (const cmat &U, const std::initializer list< idx > &target, std::string name={})

Applies the single qudit gate U on every qudit listed in target.

QCircuit & gate fan (const cmat &U, std::string name={})

Applies the single qudit gate U on every remaining non-measured qudit.

QCircuit & gate_custom (const cmat &U, const std::vector < idx > &target, std::string name={})

Jointly applies the custom multiple qudit gate U on the qudit indexes specified by target.

QCircuit & QFT (const std::vector < idx > &target, bool swap=true)

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & QFT (const std::initializer_list< idx > &target, bool swap=true)

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & QFT (bool swap=true)

Applies the quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

QCircuit & TFQ (const std::vector < idx > &target, bool swap QPP UNUSED =true)

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & TFQ (const std::initializer_list< idx > &target, bool swap=true)

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & TFQ (bool swap=true)

Applies the inverse quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

QCircuit & CTRL (const cmat &U, idx ctrl, idx target, std::string name={})

Applies the single qudit controlled gate U with control qudit ctrl and target qudit target.

QCircuit & CTRL (const cmat &U, idx ctrl, const std::vector < idx > &target, std::string name={})

Applies the single qudit controlled gate U with control qudit ctrl on every qudit listed in target.

• QCircuit & CTRL (const cmat &U, const std::vector< idx > &ctrl, idx target, std::string name={})

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on the target qudit target.

QCircuit & CTRL (const cmat &U, const std::vector< idx > &ctrl, const std::vector< idx > &target, std::string name={})

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on every qudit listed in target.

QCircuit & CTRL_custom (const cmat &U, const std::vector< idx > &ctrl, const std::vector< idx > &target, std::string name={})

Jointly applies the custom multiple-qudit controlled gate U with multiple control qudits listed in ctrl on the qudit indexes specified by target.

• QCircuit & cCTRL (const cmat &U, idx ctrl dit, idx target, std::string name={})

Applies the single qubit controlled gate U with classical control dit ctrl and target qudit target.

QCircuit & cCTRL (const cmat &U, idx ctrl_dit, const std::vector< idx > &target, std::string name={})

Applies the single qudit controlled gate U with classical control dit ctrl on every qudit listed in target.

QCircuit & cCTRL (const cmat &U, const std::vector < idx > &ctrl dits, idx target, std::string name={})

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on the target qudit target.

QCircuit & cCTRL (const cmat &U, const std::vector< idx > &ctrl_dits, const std::vector< idx > &target, std::string name={})

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on every qudit listed in target.

QCircuit & cCTRL_custom (const cmat &U, const std::vector< idx > &ctrl_dits, const std::vector< idx > &target, std::string name={})

Jointly applies the custom multiple-qudit controlled gate U with multiple classical control dits listed in ctrl on the qudit indexes specified by target.

QCircuit & measureZ (idx target, idx c_reg, std::string name={})

Measurement of single qudit in the computational basis (Z-basis)

• QCircuit & measureV (const cmat &V, idx target, idx c_reg, std::string name={})

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

QCircuit & measureV (const cmat &V, const std::vector< idx > &target, idx c reg, std::string name={})

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

• QCircuit & nop ()

No operation (no-op)

std::string to_JSON (bool enclosed_in_curly_brackets=true) const override

qpp::IJOSN::to_JSON() override

Private Member Functions

void add_hash_ (const cmat &U, std::size_t hashU)

Adds matrix to the hash table.

const std::vector< MeasureStep > & get_measurements_ () const noexcept

Vector of qpp::QCircuit::MeasureStep.

const std::vector < GateStep > & get_gates_ () const noexcept

Vector of qpp::QCircuit::GateStep.

const std::unordered_map< std::size_t, cmat > & get_cmat_hash_tbl_ () const noexcept

Hash table with the matrices used in the circuit.

std::ostream & display (std::ostream &os) const override

qpp::IDisplay::display() override

Private Attributes

• const idx nq_

number of qudits

const idx nc_

number of classical "dits"

const idx d

qudit dimension

std::string name_

optional circuit name

std::vector< bool > measured

keeps track of the measured qudits

std::unordered_map< std::size_t, cmat > cmat_hash_tbl_{{}}

```
    std::unordered_map< std::string, idx > count_ {}
        gate counts
    std::unordered_map< std::string, idx > measurement_count_ {}
        measurement counts
    std::vector< GateStep > gates_ {}
        gates
    std::vector< MeasureStep > measurements_ {}
        measurements
    std::vector< StepType > step_types_ {}
        type of each step
```

Friends

- class QEngine
- std::ostream & operator << (std::ostream &os, const GateType &gate_type)

 Extraction operator overload for qpp::QCircuit::GateType enum class.
- std::ostream & operator << (std::ostream &os, const GateStep &gate_step)

 Extraction operator overload for qpp::QCircuit::GateStep class.
- std::ostream & operator << (std::ostream &os, const MeasureType &measure_type)

 Extraction operator overload for qpp::QCircuit::MeasureType enum class.
- std::ostream & operator << (std::ostream &os, const MeasureStep &measure_step) Extraction operator overload for qpp::QCircuit::MeasureStep class.

7.54.1 Detailed Description

Quantum circuit class.

See also

qpp::QEngine

7.54.2 Member Typedef Documentation

```
7.54.2.1 const_iterator
```

using qpp::QCircuit::const_iterator = iterator

both iterators are const iterators

7.54.3 Member Enumeration Documentation

7.54.3.1 GateType

```
enum qpp::QCircuit::GateType [strong]
```

Type of gate being executed in a gate step.

Enumerator

NONE	represents no gate
SINGLE	unitary gate on a single qudit
TWO	unitary gate on 2 qudits
THREE	unitary gate on 3 qudits
CUSTOM	custom gate on multiple qudits
FAN	same unitary gate on multiple qudits
SINGLE_CTRL_SINGLE_TARGET	controlled 1 qudit unitary gate with one control and one target
SINGLE_CTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with one control and multiple targets
MULTIPLE_CTRL_SINGLE_TARGET	controlled 1 qudit unitary gate with multiple controls and single target
MULTIPLE_CTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with multiple controls and multiple targets
CUSTOM_CTRL	custom controlled gate with multiple controls and multiple targets
SINGLE_cCTRL_SINGLE_TARGET	controlled 1 qudit unitary gate with one classical control and one target
SINGLE_cCTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with one classical control and multiple targets
MULTIPLE_cCTRL_SINGLE_TARGET	controlled 1 qudit unitary gate with multiple classical controls and single target
MULTIPLE_cCTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with multiple classical controls and multiple targets
CUSTOM_cCTRL	custom controlled gate with multiple controls and multiple targets

7.54.3.2 MeasureType

```
enum qpp::QCircuit::MeasureType [strong]
```

Type of measurement being executed in a measurement step.

Enumerator

NONE	represents no measurement
MEASURE_Z	Z measurement of single qudit.
MEASURE_V	measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix ${\it V}$
MEASURE_V_MANY	measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix $\it V$

7.54.3.3 StepType

enum qpp::QCircuit::StepType [strong]

Types of each step in the quantum circuit.

Enumerator

NONE	represents no step
GATE	quantum gate(s)
MEASUREMENT	measurement
NOP	no-op

7.54.4 Constructor & Destructor Documentation

7.54.4.1 QCircuit()

```
qpp::QCircuit::QCircuit (
    idx nq,
    idx nc = 0,
    idx d = 2,
    std::string name = {} ) [inline], [explicit]
```

Constructs a quantum circuit.

Note

The measurement results can only be stored in the classical dits of which number is specified by *nc*

Parameters

nq	Number of qbits	
nc	Number of classical dits (optional)	
d	Subsystem dimensions (optional, default is qubit, i.e. $d = 2$	
name	Circuit name (optional)	

7.54.4.2 ~QCircuit()

```
\label{eq:continuit} \mbox{virtual qpp::QCircuit::$$\sim$QCircuit ( ) [virtual], [default]$}
```

Default virtual destructor.

7.54.5 Member Function Documentation

7.54.5.1 add_hash_()

Adds matrix to the hash table.

Note

Throws if a hash collision is detected., i.e., if two different matrices have the same hash

Parameters

U	Complex matrix
hashU	Hash value of U

```
7.54.5.2 begin() [1/2]
```

```
iterator qpp::QCircuit::begin ( ) [inline]
```

Iterator to the first element.

Returns

Iterator to the first element

```
7.54.5.3 begin() [2/2]
```

```
const_iterator qpp::QCircuit::begin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

```
7.54.5.4 cbegin()
```

```
const_iterator qpp::QCircuit::cbegin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

```
7.54.5.5 cCTRL() [1/4]
```

Applies the single qubit controlled gate *U* with classical control dit *ctrl* and target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

const std::vector< idx > & target,
std::string name = {}) [inline]

Applies the single qudit controlled gate *U* with classical control dit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the classical control dits
name	Optional gate name

Returns

Reference to the current instance

```
const std::vector< idx > & ctrl_dits,
idx target,
std::string name = {} ) [inline]
```

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.8 cCTRL() [4/4]
```

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the classical control dits
name	Optional gate name

Returns

Reference to the current instance

7.54.5.9 cCTRL_custom()

```
const std::vector< idx > & target,
std::string name = {} ) [inline]
```

Jointly applies the custom multiple-qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the qudit indexes specified by *target*.

Parameters

U	Multiple-qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit indexes where the gate U is applied depending on the values of the classical control dits
name	Optional gate name

Returns

Reference to the current instance

7.54.5.10 cend()

```
const_iterator qpp::QCircuit::cend ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

Returns

Constant iterator to the next to the last element

```
7.54.5.11 CTRL() [1/4]
```

Applies the single qudit controlled gate *U* with control qudit *ctrl* and target qudit *target*.

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with control qudit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.13 CTRL() [3/4]
```

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the target qudit *target*.

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

7.54.5.15 CTRL_custom()

Jointly applies the custom multiple-qudit controlled gate U with multiple control qudits listed in ctrl on the qudit indexes specified by target.

U	Multiple-qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes where the gate U is applied depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.16 display()
```

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the quantum circuit

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.54.5.17 end() [1/2] iterator qpp::QCircuit::end ( ) [inline]
```

Iterator to the next to the last element.

Returns

Iterator to the next to the last element

```
7.54.5.18 end() [2/2]
const_iterator qpp::QCircuit::end ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

Returns

Constant iterator to the next to the last element

Applies the single qudit gate U on single qudit i.

Parameters

U	Single qudit quantum gate
i	Qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the two qudit gate U on qudits i and j.

Parameters

U	Two qudit quantum gate
i	Qudit index
j	Qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the three qudit gate U on qudits i, j and k.

U	Three qudit quantum gate	
i	Qudit index	
Generated b	Generated by Doxygen	
k	Qudit index	
name	Optional gate name	

Returns

Reference to the current instance

7.54.5.22 gate_custom()

Jointly applies the custom multiple qudit gate *U* on the qudit indexes specified by *target*.

Parameters

U	Multiple qudit quantum gate
target	Subsystem indexes where the gate <i>U</i> is applied
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.23 gate_fan() [1/3]
```

Applies the single qudit gate *U* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
target Target qudit indexes; the gate U is applied on every one	
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.24 gate_fan() [2/3]
```

Applies the single qudit gate *U* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate	
target	Target qudit indexes; the gate <i>U</i> is applied on every one of them	
name	Optional gate name	

Returns

Reference to the current instance

```
7.54.5.25 gate_fan() [3/3]
```

Applies the single qudit gate U on every remaining non-measured qudit.

Parameters

U	Single qudit quantum gate
name	Optional gate name

Returns

Reference to the current instance

7.54.5.26 get_cmat_hash_tbl_()

```
const std::unordered_map<std::size_t, cmat>& qpp::QCircuit::get_cmat_hash_tbl_ ( ) const
[inline], [private], [noexcept]
```

Hash table with the matrices used in the circuit.

Returns

Hash table with the matrices used in the circuit

```
7.54.5.27 get_d()
```

```
idx qpp::QCircuit::get_d ( ) const [inline], [noexcept]
```

Dimension of the comprising qudits.

Returns

Qudit dimension

7.54.5.28 get_gate_count()

Quantum circuit gate count.

Note

If name is empty (default), returns the total gate count of the circuit

Parameters

name	Gate name (optional)
------	----------------------

Returns

Gate count

7.54.5.29 get_gate_depth()

Quantum circuit gate depth.

Note

If name is empty (default), returns the total gate depth of the circuit

name	Gate name	(ontional)
Harric	Gate Harrie	(Optional)

Returns

Gate depth

```
7.54.5.30 get_gates_()
const std::vector<GateStep>& qpp::QCircuit::get_gates_ ( ) const [inline], [private], [noexcept]
```

Returns

Vector of qpp::QCircuit::GateStep

Vector of qpp::QCircuit::GateStep.

Check whether qudit *i* was already measured.

Parameters

```
i Qudit index
```

Returns

True if qudit i was already measured, false othwewise

```
7.54.5.32 get_measured() [2/2]
std::vector<idx> qpp::QCircuit::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

```
7.54.5.33 get_measurement_count() [1/2]
```

```
idx qpp::QCircuit::get_measurement_count ( ) const [inline], [noexcept]
```

Quantum circuit total measurement count.

Returns

Total measurement count

```
7.54.5.34 get_measurement_count() [2/2]
```

Quantum circuit measurement count.

Parameters

name	Measurement name
------	------------------

Returns

Measurement count

```
7.54.5.35 get_measurements_()
```

```
\verb|const| std::vector<| MeasureStep>& qpp::QCircuit::get_measurements_ ( ) const [inline], [private], [noexcept] \\
```

Vector of qpp::QCircuit::MeasureStep.

Returns

Vector of qpp::QCircuit::MeasureStep

```
7.54.5.36 get_name()
```

```
std::string qpp::QCircuit::get_name ( ) const [inline]
```

Quantum circuit name.

Returns

Quantum circuit name

```
7.54.5.37 get_nc()
idx qpp::QCircuit::get_nc ( ) const [inline], [noexcept]
Total number of classical dits in the circuit.
Returns
Total number of classical dits
```

```
7.54.5.38 get_non_measured()
std::vector<idx> qpp::QCircuit::get_non_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

Returns

Vector of non-measured qudit indexes

```
7.54.5.39 get_nop_count()
idx qpp::QCircuit::get_nop_count ( ) const [inline]
No-op count.
```

Returns

No-op count

```
7.54.5.40 get_nq()
idx qpp::QCircuit::get_nq ( ) const [inline], [noexcept]
```

Total number of qudits in the circuit.

Returns

Total number of qudits

7.54.5.41 get_step_count()

```
idx qpp::QCircuit::get_step_count ( ) const [inline], [noexcept]
```

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

Returns

Total (gates + measurements) count

7.54.5.42 measureV() [1/2]

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V
target	Qudit index
c_reg	Classical register where the value of the measurement is stored
name	Optional measurement name

Returns

Reference to the current instance

7.54.5.43 measureV() [2/2]

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V	
target	Target qudit indexes that are jointly measured	
c_reg	Classical register where the value of the measurement is stored	
name	Optional measurement name	Generated by Doxygen

Returns

Reference to the current instance

7.54.5.44 measureZ()

Measurement of single qudit in the computational basis (Z-basis)

Parameters

target	Qudit index
c_reg	Classical register where the value of the measurement is being stored
name	Optional measurement name, default is "Measure Z"

Returns

Reference to the current instance

7.54.5.45 nop()

```
QCircuit& qpp::QCircuit::nop ( ) [inline]
```

No operation (no-op)

Note

If the underlying step is executed on a noisy engine, then noise acts before it

Returns

Reference to the current instance

```
7.54.5.46 QFT() [1/3]
```

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

```
7.54.5.47 QFT() [2/3]
```

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

```
7.54.5.48 QFT() [3/3]
```

Applies the quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

Parameters

swap	Swaps the qubits at the end (true by default)
------	---

Returns

Reference to the current instance

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the inverse quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the inverse quantum Fourier transform is applied	
swap	Swaps the qubits at the end (true by default)	

Returns

Reference to the current instance

Applies the inverse quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

Parameters

swap	Swaps the qubits at the end (true by default)
------	---

Returns

Reference to the current instance

```
7.54.5.52 to_JSON()
```

qpp::IJOSN::to JSON() override

Displays the quantum circuit in JSON format

Parameters

enclosed_in_curly_brackets	If true, encloses the result in curly brackets
----------------------------	--

Returns

String containing the JSON representation of the quantum circuit

Implements qpp::IJSON.

7.54.6 Friends And Related Function Documentation

Extraction operator overload for qpp::QCircuit::GateType enum class.

Parameters

os	Output stream
gate_type	qpp::QCircuit::GateType enum class

Returns

Output stream

```
7.54.6.2 operator << [2/4]

std::ostream& operator << (
    std::ostream & os,</pre>
```

Extraction operator overload for qpp::QCircuit::GateStep class.

const GateStep & gate_step) [friend]

Parameters

os	Output stream
gate_step	qpp::QCircuit::GateStep class

Returns

Output stream

```
7.54.6.3 operator << [3/4]
```

Extraction operator overload for qpp::QCircuit::MeasureType enum class.

Parameters

os		Output stream
mea	sure_type	qpp::QCircuit::MeasureType enum class

Returns

Output stream

```
7.54.6.4 operator << [4/4]
```

Extraction operator overload for qpp::QCircuit::MeasureStep class.

Parameters

os	Output stream
measure_step	qpp::QCircuit::MeasureStep enum class

```
Returns
```

Output stream

```
7.54.6.5 QEngine
friend class QEngine [friend]
7.54.7 Member Data Documentation
7.54.7.1 cmat_hash_tbl_
std::unordered_map<std::size_t, cmat> qpp::QCircuit::cmat_hash_tbl_ {} [private]
hash table with the matrices used in the circuit, with [Key = idx, Value = cmat]
7.54.7.2 count_
std::unordered_map<std::string, idx> qpp::QCircuit::count_ {} [private]
gate counts
7.54.7.3 d_
const idx qpp::QCircuit::d_ [private]
qudit dimension
7.54.7.4 gates_
std::vector<GateStep> qpp::QCircuit::gates_ {} [private]
gates
```

```
7.54.7.5 measured_
std::vector<bool> qpp::QCircuit::measured_ [private]
keeps track of the measured qudits
7.54.7.6 measurement_count_
std::unordered_map<std::string, idx> qpp::QCircuit::measurement_count_ {} [private]
measurement counts
7.54.7.7 measurements_
std::vector<MeasureStep> qpp::QCircuit::measurements_ {} [private]
measurements
7.54.7.8 name_
std::string qpp::QCircuit::name_ [private]
optional circuit name
7.54.7.9 nc
const idx qpp::QCircuit::nc_ [private]
number of classical "dits"
7.54.7.10 nq_
const idx qpp::QCircuit::nq_ [private]
number of qudits
```

7.54.7.11 step_types_

```
std::vector<StepType> qpp::QCircuit::step_types_ {} [private]
```

type of each step

The documentation for this class was generated from the following file:


• classes/circuits/circuits.h

7.55 qpp::QEngine Class Reference


Quantum circuit engine, executes qpp::QCircuit.

#include <classes/circuits/engines.h>

Inheritance diagram for qpp::QEngine:



Collaboration diagram for qpp::QEngine:



Public Member Functions

QEngine (const QCircuit &qc)

Constructs a quantum engine out of a quantum circuit.

• QEngine (const QEngine &)=default

Default copy constructor.

• QEngine & operator= (const QEngine &)=default

Default copy assignment operator.

• QEngine (QCircuit &&)=delete

Disables rvalue QCircuit.

virtual ~QEngine ()=default

Default virtual destructor.

• ket get_psi () const

Underlying quantum state.

std::vector < idx > get_dits () const

Vector with the values of the underlying classical dits.

• idx get_dit (idx i) const

Value of the classical dit at position i.

• std::vector< double > get_probs () const

Vector of underlying measurement outcome probabilities.

bool get_measured (idx i) const

Check whether qudit i was already measured.

std::vector< idx > get_measured () const

Vector of already measured qudit indexes.

std::vector< idx > get_non_measured () const

Vector of non-measured qudit indexes.

const QCircuit & get_circuit () const noexcept

Quantum circuit.

QEngine & set_dit (idx i, idx value)

Sets the classical dit at position i.

QEngine & set_psi (const ket &psi)

Sets the underlying quantum state to psi.

void reset ()

Resets the engine.

virtual void execute (const QCircuit::iterator::value_type &elem)

Executes one step in the quantum circuit.

• void execute (const QCircuit::iterator &it)

Executes one step in the quantum circuit.

• void execute ()

Executes the entire quantum circuit.

• std::string to_JSON (bool enclosed_in_curly_brackets=true) const override

qpp::IJOSN::to_JSON() override

Protected Member Functions

• void set_measured_ (idx i)

Marks qudit i as measured then re-label accordingly the remaining non-measured qudits.

std::vector< idx > get_relative_pos_ (std::vector< idx > v)

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

Protected Attributes

```
    const QCircuit * qc_
        pointer to constant quantum circuit
    ket psi_
        state vector
    std::vector< idx > dits_
        classical dits
    std::vector< double > probs_
        measurement probabilities
    std::vector< idx > subsys_
        relabel them after measurements
```

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display() override*

7.55.1 Detailed Description

Quantum circuit engine, executes qpp::QCircuit.

See also

qpp::QCircuit

7.55.2 Constructor & Destructor Documentation

Constructs a quantum engine out of a quantum circuit.

Note

The quantum circuit must be an Ivalue

See also

```
qpp::QEngine(QCircuit&&)
```

Note

The initial underlying quantum state is set to $|0\rangle^{\otimes n}$

Parameters

```
qc Quantum circuit
```

Default copy constructor.

Disables rvalue QCircuit.

7.55.2.4 ~QEngine()

```
virtual qpp::QEngine::~QEngine ( ) [virtual], [default]
```

Default virtual destructor.

7.55.3 Member Function Documentation

```
7.55.3.1 display()
```

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the state of the engine

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

Executes one step in the quantum circuit.

Parameters

```
elem Step to be executed
```

Reimplemented in qpp::QNoisyEngine < NoiseModel >.

Executes one step in the quantum circuit.

Parameters

it Iterator to the step to be executed

```
7.55.3.4 execute() [3/3]
void qpp::QEngine::execute ( ) [inline]
```

Executes the entire quantum circuit.

```
7.55.3.5 get_circuit()
const QCircuit& qpp::QEngine::get_circuit ( ) const [inline], [noexcept]
```

Quantum circuit.

Returns

Underlying quantum circuit

7.55.3.6 get_dit()

```
idx qpp::QEngine::get_dit (
        idx i ) const [inline]
```

Value of the classical dit at position i.

Parameters

i Classical dit index

Returns

Value of the classical dit at position i

7.55.3.7 get_dits()

```
std::vector<idx> qpp::QEngine::get_dits ( ) const [inline]
```

Vector with the values of the underlying classical dits.

Returns

Vector of underlying classical dits

7.55.3.8 get_measured() [1/2]

```
bool qpp::QEngine::get_measured (
        idx i ) const [inline]
```

Check whether qudit \emph{i} was already measured.

Parameters

i Qudit index

Returns

True if qudit *i* was already measured, false othwewise

```
7.55.3.9 get_measured() [2/2]
std::vector<idx> qpp::QEngine::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

```
7.55.3.10 get_non_measured()
```

```
std::vector<idx> qpp::QEngine::get_non_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

Returns

Vector of non-measured qudit indexes

```
7.55.3.11 get_probs()
```

```
std::vector<double> qpp::QEngine::get_probs ( ) const [inline]
```

Vector of underlying measurement outcome probabilities.

Those should be interpreted as conditional probabilities based on the temporal order of the measurements, i.e. if we measure qubit 0, then measure qubit 1, and finally qubit 2, the resulting vector of outcome probabilities probs[2] should be interpreted as the conditional probability of qubit 2 having the outcome it had given that qubit 1 and qubit 0 had their given outcomes, respectively. As an example, if we measure the qubit 0 followed by the qubit 1 of a maximally entangled state $(|00\rangle + |11\rangle)/\sqrt{2}$, then the vector of outcome probabilities will be [0.5, 1].

Note

The probability vector has the same length as the vector of classical dits. If the measurement result is stored at the index c_reg , then the outcome probability is automatically stored at the same index c_reg in the probability vector.

Returns

Vector of underlying measurement outcome probabilities

```
7.55.3.12 get_psi()
```

```
ket qpp::QEngine::get_psi ( ) const [inline]
```

Underlying quantum state.

Returns

Underlying quantum state

7.55.3.13 get_relative_pos_()

```
\label{eq:condition} $$ $td::vector < idx> qpp::QEngine::get_relative_pos_ ($$ std::vector < idx>v ) [inline], [protected]
```

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

Parameters



Returns

Vector of qudit indexes

7.55.3.14 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

7.55.3.15 reset()

```
void qpp::QEngine::reset ( ) [inline]
```

Resets the engine.

Re-initializes everything to zero and sets the initial state to $|0\rangle^{\otimes n}$

```
7.55.3.16 set_dit()
```

Sets the classical dit at position i.

Parameters

i	Classical dit index
value	Classical dit value

Returns

Reference to the current instance

7.55.3.17 set_measured_()

```
void qpp::QEngine::set_measured_ (
          idx i ) [inline], [protected]
```

Marks qudit *i* as measured then re-label accordingly the remaining non-measured qudits.

Parameters

i Qudit index

7.55.3.18 set_psi()

Sets the underlying quantum state to psi.

Note

The order is lexicographical with respect to the remaining non-measured qudits

Parameters

psi State vector

Returns

Reference to the current instance

```
7.55.3.19 to_JSON()
```

qpp::IJOSN::to_JSON() override

Displays the state of the engine in JSON format

Parameters

Returns

String containing the JSON representation of the state of the engine

Implements qpp::IJSON.

7.55.4 Member Data Documentation

```
7.55.4.1 dits_
std::vector<idx> qpp::QEngine::dits_ [protected]
classical dits
```

```
7.55.4.2 probs_
std::vector<double> qpp::QEngine::probs_ [protected]
```

measurement probabilities

```
7.55.4.3 psi_
ket qpp::QEngine::psi_ [protected]
state vector
```

```
7.55.4.4 qc_
```

```
const QCircuit* qpp::QEngine::qc_ [protected]
```

pointer to constant quantum circuit

7.55.4.5 subsys_

```
std::vector<idx> qpp::QEngine::subsys_ [protected]
```

relabel them after measurements

keeps track of the measured subsystems,

The documentation for this class was generated from the following file:


· classes/circuits/engines.h

7.56 qpp::QNoisyEngine < NoiseModel > Class Template Reference


Noisy quantum circuit engine, executes qpp::QCircuit.

```
#include <classes/circuits/engines.h>
```

Inheritance diagram for qpp::QNoisyEngine < NoiseModel >:



Collaboration diagram for qpp::QNoisyEngine < NoiseModel >:



Public Member Functions

• QNoisyEngine (const QCircuit &qc, const NoiseModel &noise)

Constructs a noisy quantum engine out of a quantum circuit.

void execute (const QCircuit::iterator::value_type &elem) override

Executes one step in the quantum circuit.

• std::vector< std::vector< idx >> get_noise_results () const

Vector of noise results obtained before every step in the circuit.

virtual void execute (const QCircuit::iterator::value_type &elem)

Executes one step in the quantum circuit.

• void execute (const QCircuit::iterator &it)

Executes one step in the quantum circuit.

• void execute ()

Executes the entire quantum circuit.

Private Attributes

const NoiseModel noise

quantum noise model

std::vector< std::vector< idx >> noise_results_

noise results

Additional Inherited Members

7.56.1 Detailed Description

$$\label{local_total_constraints} \begin{split} & \text{template} \! < \! \text{typename NoiseModel} \! > \\ & \text{class qpp::QNoisyEngine} \! < \! \text{NoiseModel} \! > \end{split}$$

Noisy quantum circuit engine, executes qpp::QCircuit.

See also

qpp::QCircuit, qpp::NoiseBase

Assumes an uncorrelated noise model that is applied to each non-measured qubit before every step in the logical circuit

Template Parameters

NoiseModel Quantum noise model, should be derived from qpp::No	seBase
--	--------

7.56.2 Constructor & Destructor Documentation

7.56.2.1 QNoisyEngine()

Constructs a noisy quantum engine out of a quantum circuit.

Parameters

qc	Quantum circuit
noise	Quantum noise model

7.56.3 Member Function Documentation

```
7.56.3.1 execute() [1/4]

template<typename NoiseModel >
virtual void qpp::QEngine::execute [inline]
```

Executes one step in the quantum circuit.

Parameters

lem Step to be executed

```
7.56.3.2 execute() [2/4]
```

```
template<typename NoiseModel >
void qpp::QEngine::execute [inline]
```

Executes the entire quantum circuit.

7.56.3.3 execute() [3/4]

```
template<typename NoiseModel >
void qpp::QEngine::execute [inline]
```

Executes one step in the quantum circuit.

Parameters

```
it Iterator to the step to be executed
```

```
7.56.3.4 execute() [4/4]
```

Executes one step in the quantum circuit.

Parameters

```
elem Step to be executed
```

Reimplemented from qpp::QEngine.

7.56.3.5 get_noise_results()

```
template<typename NoiseModel >
std::vector<std::vector<idx> > qpp::QNoisyEngine< NoiseModel >::get_noise_results ( ) const
[inline]
```

Vector of noise results obtained before every step in the circuit.

The first vector contains the noise measurement results obtained before applying the first step in the circuit, and so on, ordered by non-measured qudits. That is, the first element in the vector corresponding to noise obtained before a given step in the circuit represents the noise result obtained on the first non-measured qudit etc.

Returns

Vector of noise results

7.56.4 Member Data Documentation

7.56.4.1 noise_

```
template<typename NoiseModel >
const NoiseModel qpp::QNoisyEngine< NoiseModel >::noise_ [private]
```

quantum noise model

7.56.4.2 noise_results_

```
template<typename NoiseModel >
std::vector<std::vector<idx> > qpp::QNoisyEngine< NoiseModel >::noise_results_ [private]
```

noise results

The documentation for this class was generated from the following file:


· classes/circuits/engines.h

7.57 qpp::QubitAmplitudeDampingNoise Class Reference


Qubit amplitude damping noise, as described in Nielsen and Chuang.

```
#include <classes/noise.h>
```

 $Inheritance\ diagram\ for\ qpp:: Qubit Amplitude Damping Noise:$



Collaboration diagram for qpp::QubitAmplitudeDampingNoise:



Public Member Functions

QubitAmplitudeDampingNoise (double gamma)
 Qubit amplitude damping noise constructor.

Additional Inherited Members

7.57.1 Detailed Description

Qubit amplitude damping noise, as described in Nielsen and Chuang.

7.57.2 Constructor & Destructor Documentation

7.57.2.1 QubitAmplitudeDampingNoise()

Qubit amplitude damping noise constructor.

Parameters

gamma	Amplitude damping coefficient

The documentation for this class was generated from the following file:


· classes/noise.h

7.58 qpp::QubitBitFlipNoise Class Reference


Qubit bit flip noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitBitFlipNoise:



 $Collaboration\ diagram\ for\ qpp::Qubit Bit Flip Noise:$



Public Member Functions

QubitBitFlipNoise (double p)
 Qubit bit flip noise constructor.

Additional Inherited Members

7.58.1 Detailed Description

Qubit bit flip noise.

7.58.2 Constructor & Destructor Documentation

7.58.2.1 QubitBitFlipNoise()

Qubit bit flip noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.59 qpp::QubitBitPhaseFlipNoise Class Reference


Qubit bit-phase flip (dephasing) noise.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitBitPhaseFlipNoise:



Collaboration diagram for qpp::QubitBitPhaseFlipNoise:



Public Member Functions

QubitBitPhaseFlipNoise (double p)
 Qubit bit-phase flip noise constructor.

Additional Inherited Members

7.59.1 Detailed Description

Qubit bit-phase flip (dephasing) noise.

7.59.2 Constructor & Destructor Documentation

7.59.2.1 QubitBitPhaseFlipNoise()

```
\label{eq:qpp::QubitBitPhaseFlipNoise::QubitBitPhaseFlipNoise (} \\ \mbox{double } p \mbox{ ) [inline], [explicit]}
```

Qubit bit-phase flip noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.60 qpp::QubitDepolarizingNoise Class Reference


Qubit depolarizing noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitDepolarizingNoise:



Collaboration diagram for qpp::QubitDepolarizingNoise:



Public Member Functions

QubitDepolarizingNoise (double p)
 Qubit depolarizing noise constructor.

Additional Inherited Members

7.60.1 Detailed Description

Qubit depolarizing noise.

7.60.2 Constructor & Destructor Documentation

7.60.2.1 QubitDepolarizingNoise()

```
\label{eq:qpp::QubitDepolarizingNoise::QubitDepolarizingNoise (} \\ \text{double } p \text{ ) } \quad \text{[inline], [explicit]}
```

Qubit depolarizing noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.61 qpp::QubitPhaseDampingNoise Class Reference


Qubit phase damping noise, as described in Nielsen and Chuang.

```
#include <classes/noise.h>
```

 $Inheritance\ diagram\ for\ qpp:: Qubit Phase Damping Noise:$



Collaboration diagram for qpp::QubitPhaseDampingNoise:



Public Member Functions

QubitPhaseDampingNoise (double lambda)
 Qubit phase damping noise constructor.

Additional Inherited Members

7.61.1 Detailed Description

Qubit phase damping noise, as described in Nielsen and Chuang.

7.61.2 Constructor & Destructor Documentation

7.61.2.1 QubitPhaseDampingNoise()

Qubit phase damping noise constructor.

Parameters

lambda	Phase damping coefficient

The documentation for this class was generated from the following file:


· classes/noise.h

7.62 qpp::QubitPhaseFlipNoise Class Reference


Qubit phase flip (dephasing) noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitPhaseFlipNoise:



Collaboration diagram for qpp::QubitPhaseFlipNoise:



Public Member Functions

QubitPhaseFlipNoise (double p)
 Qubit phase flip (dephasing) noise constructor.

Additional Inherited Members

7.62.1 Detailed Description

Qubit phase flip (dephasing) noise.

7.62.2 Constructor & Destructor Documentation

7.62.2.1 QubitPhaseFlipNoise()

Qubit phase flip (dephasing) noise constructor.

Parameters

```
p Noise probability
```

The documentation for this class was generated from the following file:


· classes/noise.h

7.63 qpp::exception::QuditAlreadyMeasured Class Reference


Qudit was already measured exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::QuditAlreadyMeasured:



Collaboration diagram for qpp::exception::QuditAlreadyMeasured:



Public Member Functions

- std::string description () const override
 - Exception description.
- Exception (const std::string &where)

Constructs an exception.

7.63.1 Detailed Description

Qudit was already measured exception.

The qudit was already measured and cannot be measured again

7.63.2 Member Function Documentation

7.63.2.1 description()

std::string qpp::exception::QuditAlreadyMeasured::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.63.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.64 qpp::QuditDepolarizingNoise Class Reference


Qudit depolarizing noise.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QuditDepolarizingNoise:



Collaboration diagram for qpp::QuditDepolarizingNoise:



Public Member Functions

QuditDepolarizingNoise (double p, idx d)
 Qudit depolarizing noise constructor.

Private Member Functions

• std::vector< cmat > fill_Ks_ (idx d) const

Fills the Kraus operator vector.

std::vector< double > fill_probs_ (double p, idx d) const
 Fills the probability vector.

Additional Inherited Members

7.64.1 Detailed Description

Qudit depolarizing noise.

7.64.2 Constructor & Destructor Documentation

7.64.2.1 QuditDepolarizingNoise()

```
qpp::QuditDepolarizingNoise::QuditDepolarizingNoise ( double p,  idx \ d \ ) \ \ [inline], \ [explicit]
```

Qudit depolarizing noise constructor.

Parameters

р	Noise probability
d	Qudit dimension

7.64.3 Member Function Documentation

```
7.64.3.1 fill_Ks_()
```

Fills the Kraus operator vector.

Parameters

```
d Qudit dimension
```

Returns

Vector of Kraus operators representing the depolarizing noise

```
7.64.3.2 fill_probs_()
```

```
\label{eq:continuous} $$ std::vector<double> qpp::QuditDepolarizingNoise::fill_probs_ ($ double p, $ idx d ) const [inline], [private] $$
```

Fills the probability vector.

Parameters

р	Probability
d	Qudit dimension

Returns

Probability vector

The documentation for this class was generated from the following file:


· classes/noise.h

7.65 qpp::RandomDevices Class Reference


Singleton class that manages the source of randomness in the library.

#include <classes/random_devices.h>

Inheritance diagram for qpp::RandomDevices:



Collaboration diagram for qpp::RandomDevices:



Public Member Functions

• std::mt19937 & get_prng ()

Returns a reference to the internal PRNG object.

std::istream & load (std::istream &is)

Loads the state of the PRNG from an input stream.

• std::ostream & save (std::ostream &os) const

Saves the state of the PRNG to an output stream.

Private Member Functions

• RandomDevices ()

Initializes and seeds the random number generators.

∼RandomDevices ()=default

Default destructor.

Private Attributes

 std::random_device rd_ used to seed std::mt19937 prng_

std::mt19937 prng_

Mersenne twister random number generator.

Friends

class internal::Singleton < RandomDevices >

Additional Inherited Members

7.65.1 Detailed Description

Singleton class that manages the source of randomness in the library.

Consists of a wrapper around an std::mt19937 Mersenne twister random number generator engine and an std
∴:random_device engine. The latter is used to seed the Mersenne twister.

Warning

This class DOES NOT seed the standard C number generator used by Eigen::Matrix::Random(), since it is not thread safe. Do not use Eigen::Matrix::Random() or functions that depend on the C style random number engine, but use qpp::rand() instead!

7.65.2 Constructor & Destructor Documentation

7.65.2.1 RandomDevices()

```
qpp::RandomDevices::RandomDevices ( ) [inline], [private]
```

Initializes and seeds the random number generators.

```
7.65.2.2 ~RandomDevices()
```

```
\verb"qpp::RandomDevices::$\sim$RandomDevices ( ) [private], [default]
```

Default destructor.

7.65.3 Member Function Documentation

```
7.65.3.1 get_prng()
```

```
std::mt19937& qpp::RandomDevices::get_prng ( ) [inline]
```

Returns a reference to the internal PRNG object.

Returns

Reference to the internal PRNG object

7.65.3.2 load()

```
std::istream& qpp::RandomDevices::load (  \texttt{std::istream \& } is \ ) \quad [inline]
```

Loads the state of the PRNG from an input stream.

Parameters

```
is Input stream
```

Returns

The input stream

7.65.3.3 save()

Saves the state of the PRNG to an output stream.

Parameters

os	Output stream
----	---------------

Returns

The output stream

7.65.4 Friends And Related Function Documentation

```
7.65.4.1 internal::Singleton < RandomDevices >
```

```
friend class internal::Singleton< RandomDevices > [friend]
```

7.65.5 Member Data Documentation

```
7.65.5.1 prng_
```

```
std::mt19937 qpp::RandomDevices::prng_ [private]
```

Mersenne twister random number generator.

```
7.65.5.2 rd_
```

```
std::random_device qpp::RandomDevices::rd_ [private]
```

used to seed std::mt19937 prng_

The documentation for this class was generated from the following file:

• classes/random_devices.h

7.66 qpp::internal::Singleton < T > Class Template Reference

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

```
#include <internal/classes/singleton.h>
```

Static Public Member Functions

- static T & get_instance () noexcept(std::is_nothrow_constructible < T >::value)
- static T & get_thread_local_instance () noexcept(std::is_nothrow_constructible < T >::value)

Protected Member Functions

- Singleton () noexcept=default
- Singleton (const Singleton &)=delete
- Singleton & operator= (const Singleton &)=delete
- virtual ∼Singleton ()=default

7.66.1 Detailed Description

```
\label{template} \begin{tabular}{ll} template < typename T > \\ class & qpp::internal::Singleton < T > \\ \end{tabular}
```

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

To implement a singleton, derive your class from qpp::internal::Singleton, make qpp::internal::Singleton a friend of your class, then declare the constructor and destructor of your class as private. To get an instance, use the static member function qpp::internal::Singleton::get_instance() (qpp::internal::Singleton::get_thread_local_instance()), which returns a reference (thread_local_reference) to your newly created singleton (thread-safe in C++11).

Example:

See also

Code of qpp::Codes, qpp::Gates, qpp::Init, qpp::RandomDevices, qpp::States or qpp.h for real world examples of usage.

7.66.2 Constructor & Destructor Documentation

```
7.66.2.1 Singleton() [1/2]
template<typename T>
qpp::internal::Singleton < T >::Singleton ( ) [protected], [default], [noexcept]
7.66.2.2 Singleton() [2/2]
template<typename T>
qpp::internal::Singleton < T >::Singleton (
             const Singleton< T > \& ) [protected], [delete]
7.66.2.3 ∼Singleton()
template<typename T>
virtual qpp::internal::Singleton < T >::~Singleton ( ) [protected], [virtual], [default]
7.66.3 Member Function Documentation
7.66.3.1 get_instance()
template<typename T>
\texttt{static} \ \texttt{T\& qpp::internal::Singleton} < \ \texttt{T} \ > :: \texttt{get\_instance} \ ( \ ) \quad \texttt{[inline], [static], [noexcept]}
7.66.3.2 get_thread_local_instance()
template<typename T>
static T& qpp::internal::Singleton< T >::get_thread_local_instance ( ) [inline], [static],
[noexcept]
7.66.3.3 operator=()
template<typename T>
Singleton& qpp::internal::Singleton< T >::operator= (
              const Singleton< T > \& ) [protected], [delete]
```

The documentation for this class was generated from the following file:


• internal/classes/singleton.h

7.67 qpp::exception::SizeMismatch Class Reference


Size mismatch exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SizeMismatch:



Collaboration diagram for qpp::exception::SizeMismatch:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.67.1 Detailed Description

Size mismatch exception.

Sizes do not match

7.67.2 Member Function Documentation

7.67.2.1 description()

std::string qpp::exception::SizeMismatch::description () const [inline], [override], [virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.67.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

The documentation for this class was generated from the following file:

· classes/exception.h

7.68 qpp::NoiseType::StateDependent Class Reference

Template tag, used whenever the noise is state-dependent.

#include <classes/noise.h>

7.68.1 Detailed Description

Template tag, used whenever the noise is state-dependent.

The documentation for this class was generated from the following file:

· classes/noise.h

7.69 qpp::NoiseType::StateIndependent Class Reference

Template tag, used whenever the noise is state-independent.

#include <classes/noise.h>

7.69.1 Detailed Description

Template tag, used whenever the noise is state-independent.

The documentation for this class was generated from the following file:


classes/noise.h

7.70 qpp::States Class Reference


const Singleton class that implements most commonly used states

#include <classes/states.h>

Inheritance diagram for qpp::States:



Collaboration diagram for qpp::States:



Public Member Functions

• ket mes (idx d=2) const

Maximally entangled state of 2 qudits.

• ket zero (idx n, idx d=2) const

Zero state of n qudits.

• ket one (idx n, idx d=2) const

One state of n qudits.

• ket jn (idx j, idx n, idx d=2) const

 $|j\rangle^{\otimes n}$ state of n qudits

• ket plus (idx n) const

Plus state of n qubits.

• ket minus (idx n) const

Minus state of n qubits.

Public Attributes

```
    ket x0 {ket::Zero(2)}
```

Pauli Sigma-X 0-eigenstate |+>

ket x1 {ket::Zero(2)}

Pauli Sigma-X 1-eigenstate |->

ket y0 {ket::Zero(2)}

Pauli Sigma-Y 0-eigenstate |y+>

ket y1 {ket::Zero(2)}

Pauli Sigma-Y 1-eigenstate | y->

ket z0 {ket::Zero(2)}

Pauli Sigma-Z 0-eigenstate | 0>

ket z1 {ket::Zero(2)}

Pauli Sigma-Z 1-eigenstate | 1>

• cmat px0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

cmat px1 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.

```
    cmat py0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 0-eigenstate |y+\rangle < y+|.

    cmat py1 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.

    cmat pz0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
• cmat pz1 {cmat::Zero(2, 2)}
      Projector onto the Pauli Sigma-Z 1-eigenstate |1><1|.
ket b00 {ket::Zero(4)}
      Bell-00 state, as described in Nielsen and Chuang.

    ket b01 {ket::Zero(4)}

      Bell-01 state, as described in Nielsen and Chuang.

    ket b10 {ket::Zero(4)}

      Bell-10 state, as described in Nielsen and Chuang.
ket b11 {ket::Zero(4)}
      Bell-11 state, as described in Nielsen and Chuang.

    cmat pb00 {cmat::Zero(4, 4)}

      Projector onto the Bell-00 state.

    cmat pb01 {cmat::Zero(4, 4)}

      Projector onto the Bell-01 state.

    cmat pb10 {cmat::Zero(4, 4)}

      Projector onto the Bell-10 state.

    cmat pb11 {cmat::Zero(4, 4)}

      Projector onto the Bell-11 state.
ket GHZ {ket::Zero(8)}
      GHZ state.

    ket W {ket::Zero(8)}

      W state.
cmat pGHZ {cmat::Zero(8, 8)}
      Projector onto the GHZ state.
cmat pW {cmat::Zero(8, 8)}
      Projector onto the W state.
```

Private Member Functions

- States ()
- ∼States ()=default

Default destructor.

Friends

class internal::Singleton < const States >

Additional Inherited Members

7.70.1 Detailed Description

const Singleton class that implements most commonly used states

7.70.2 Constructor & Destructor Documentation

```
7.70.2.1 States()

qpp::States::States ( ) [inline], [private]

Initialize the states

7.70.2.2 ~States()
```

qpp::States::~States () [private], [default]

Default destructor.

7.70.3 Member Function Documentation

```
7.70.3.1 jn()
```

 $|j\rangle^{\otimes n}$ state of *n* qudits

Parameters

j	Non-negative integer
n	Non-negative integer
d	Subsystem dimensions

Returns

 $|j\rangle^{\otimes n}$ state of *n* qudits

7.70.3.2 mes()

```
ket qpp::States::mes (
idx d = 2 ) const [inline]
```

Maximally entangled state of 2 qudits.

Parameters

d Subsystem dimensions

Returns

Maximally entangled state $\frac{1}{\sqrt{d}} \sum_{j=0}^{d-1} |jj\rangle$ of 2 qudits

7.70.3.3 minus()

```
ket qpp::States::minus (
          idx n ) const [inline]
```

Minus state of n qubits.

Parameters

n Non-negative integer

Returns

Minus state $|-\rangle^{\otimes n}$ of n qubits

7.70.3.4 one()

```
ket qpp::States::one (
          idx n,
          idx d = 2) const [inline]
```

One state of *n* qudits.

Parameters

n	Non-negative integer
d	Subsystem dimensions

Returns

One state $|1\rangle^{\otimes n}$ of n qudits

7.70.3.5 plus()

```
ket qpp::States::plus (
         idx n ) const [inline]
```

Plus state of *n* qubits.

Parameters

```
n Non-negative integer
```

Returns

Plus state $|+\rangle^{\otimes n}$ of n qubits

7.70.3.6 zero()

```
ket qpp::States::zero (
         idx n,
         idx d = 2 ) const [inline]
```

Zero state of *n* qudits.

Parameters

n	Non-negative integer	
d	Subsystem dimensions	

Returns

Zero state $|0\rangle^{\otimes n}$ of n qudits

7.70.4 Friends And Related Function Documentation

```
7.70.4.1 internal::Singleton < const States >
```

friend class internal::Singleton< const States > [friend]

7.70.5 Member Data Documentation

```
7.70.5.1 b00
```

```
ket qpp::States::b00 {ket::Zero(4)}
```

Bell-00 state, as described in Nielsen and Chuang.

7.70.5.2 b01

```
ket qpp::States::b01 {ket::Zero(4)}
```

Bell-01 state, as described in Nielsen and Chuang.

7.70.5.3 b10

```
ket qpp::States::b10 {ket::Zero(4)}
```

Bell-10 state, as described in Nielsen and Chuang.

7.70.5.4 b11

```
ket qpp::States::b11 {ket::Zero(4)}
```

Bell-11 state, as described in Nielsen and Chuang.

7.70.5.5 GHZ

```
ket qpp::States::GHZ {ket::Zero(8)}
```

GHZ state.

7.70.5.6 pb00

```
cmat qpp::States::pb00 {cmat::Zero(4, 4)}
```

Projector onto the Bell-00 state.

```
7.70.5.7 pb01
cmat qpp::States::pb01 {cmat::Zero(4, 4)}
Projector onto the Bell-01 state.
7.70.5.8 pb10
cmat qpp::States::pb10 {cmat::Zero(4, 4)}
Projector onto the Bell-10 state.
7.70.5.9 pb11
cmat qpp::States::pb11 {cmat::Zero(4, 4)}
Projector onto the Bell-11 state.
7.70.5.10 pGHZ
cmat qpp::States::pGHZ {cmat::Zero(8, 8)}
Projector onto the GHZ state.
7.70.5.11 pW
cmat qpp::States::pW {cmat::Zero(8, 8)}
Projector onto the W state.
7.70.5.12 px0
cmat qpp::States::px0 {cmat::Zero(2, 2)}
```

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

```
7.70.5.13 px1
cmat qpp::States::px1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.
7.70.5.14 py0
cmat qpp::States::py0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 0-eigenstate |y+>< y+|.
7.70.5.15 py1
cmat qpp::States::py1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.
7.70.5.16 pz0
cmat qpp::States::pz0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
7.70.5.17 pz1
cmat qpp::States::pz1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 1-eigenstate |1><1|.
7.70.5.18 W
ket qpp::States::W {ket::Zero(8)}
W state.
```

```
7.70.5.19 x0
ket qpp::States::x0 {ket::Zero(2)}
Pauli Sigma-X 0-eigenstate |+>
7.70.5.20 x1
ket qpp::States::x1 {ket::Zero(2)}
Pauli Sigma-X 1-eigenstate |->
7.70.5.21 y0
ket qpp::States::y0 {ket::Zero(2)}
Pauli Sigma-Y 0-eigenstate |y+>
7.70.5.22 y1
ket qpp::States::y1 {ket::Zero(2)}
Pauli Sigma-Y 1-eigenstate |y->
7.70.5.23 z0
ket qpp::States::z0 {ket::Zero(2)}
Pauli Sigma-Z 0-eigenstate |0>
7.70.5.24 z1
ket qpp::States::z1 {ket::Zero(2)}
Pauli Sigma-Z 1-eigenstate |1>
The documentation for this class was generated from the following file:
```


classes/states.h

7.71 qpp::exception::SubsysMismatchDims Class Reference


Subsystems mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SubsysMismatchDims:



Collaboration diagram for qpp::exception::SubsysMismatchDims:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.71.1 Detailed Description

Subsystems mismatch dimensions exception.

std::vector<idx> of subsystem labels has duplicates, or has entries that are larger than the size of the std← ::vector<idx> of dimensions

7.71.2 Member Function Documentation

7.71.2.1 description()

std::string qpp::exception::SubsysMismatchDims::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.71.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.72 qpp::Timer < T, CLOCK_T > Class Template Reference


Chronometer.

#include <classes/timer.h>

Inheritance diagram for qpp::Timer < T, CLOCK_T >:



Collaboration diagram for qpp::Timer < T, CLOCK_T >:



Public Member Functions

• Timer () noexcept

Constructs an instance with the current time as the starting point.

• virtual \sim Timer ()=default

Default virtual destructor.

· void tic () noexcept

Resets the chronometer.

• const Timer & toc () noexcept

Stops the chronometer.

• double tics () const noexcept

Time passed in the duration specified by T.

• template<typename U = T>

U get_duration () const noexcept

Duration specified by U.

Protected Attributes

- CLOCK_T::time_point start_
- CLOCK_T::time_point end_

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display() override*

7.72.1 Detailed Description

```
template < typename\ T = std::chrono::duration < double >, typename\ CLOCK\_T = std::chrono::steady\_clock > class\ qpp::Timer < T,\ CLOCK\_T >
```

Chronometer.

Template Parameters

	Tics duration, default is std::chrono::duration <double>, i.e. seconds in double precision</double>
CLOCK←	Clock's type, default is std::chrono::steady_clock, not affected by wall clock changes during runtime
_	-

7.72.2 Constructor & Destructor Documentation

7.72.2.1 Timer()

```
\label{template} $$ \ensuremath{\texttt{template}}$ $$ \ensuremath{\texttt{typename T} = std::chrono::steady} $$ $$ \ensuremath{\texttt{clock}}$ $$ \ensuremath{\texttt{clock}}$ $$ \ensuremath{\texttt{qpp}::Timer}$ \ensuremath{\texttt{T}, CLOCK\_T} >::Timer () [inline], [noexcept] $$
```

Constructs an instance with the current time as the starting point.

7.72.2.2 \sim Timer()

```
\label{top:clock} $$ $ \end{tikzpename} $$ T = std::chrono::steady \leftarrow $$ $ \end{tikzpename} $$ CLOCK_T = std::chrono::steady \leftarrow $$ \end{tikzpename} $$ \end{tikzpename} $$ \end{tikzpename} $$ T = std::chrono::steady \leftarrow $$ \end{tikzpename} $$ \end{tikzpename} $$ \end{tikzpename} $$ \end{tikzpename} $$ T = std::chrono::steady \leftarrow $$ \end{tikzpename} $$ \end{tikzpename} $$ \end{tikzpename} $$ \end{tikzpename} $$ \end{tikzpename} $$ T = std::chrono::steady \leftarrow $$ \end{tikzpename} $$ \end{tiz
```

Default virtual destructor.

7.72.3 Member Function Documentation

7.72.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream the number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc()

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.72.3.2 get_duration()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady 
_clock>
template<typename U = T>
U qpp::Timer< T, CLOCK_T >::get_duration ( ) const [inline], [noexcept]
```

Duration specified by U.

Template Parameters

U Duration, default is T, which defaults to std::chrono::duration<double>, i.e. seconds in double precision

Returns

Duration that passed between the instantiation/reset and invocation of qpp::Timer::toc()

7.72.3.3 tic()

```
 \begin{tabular}{ll} template < type name T = std::chrono::duration < double>, type name CLOCK_T = std::chrono::steady & clock> \\ void qpp::Timer < T, CLOCK_T >::tic ( ) [inline], [noexcept] \\ \end{tabular}
```

Resets the chronometer.

Resets the starting/ending point to the current time

7.72.3.4 tics()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
double qpp::Timer< T, CLOCK_T >::tics ( ) const [inline], [noexcept]
```

Time passed in the duration specified by T.

Returns

Number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc()

7.72.3.5 toc()

```
 \begin{tabular}{ll} template < type name $T = std::chrono::steady \leftarrow \_clock > \\ const $Timer\& $qpp::Timer < T, $CLOCK_T > ::toc ( ) [inline], [noexcept] \end{tabular}
```

Stops the chronometer.

Set the current time as the ending point

Returns

Reference to the current instance

7.72.4 Member Data Documentation

7.72.4.1 end

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady←
   _clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::end_ [protected]
```

7.72.4.2 start_

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::start_ [protected]
```

The documentation for this class was generated from the following file:


· classes/timer.h

7.73 qpp::exception::TypeMismatch Class Reference


Type mismatch exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::TypeMismatch:



Collaboration diagram for qpp::exception::TypeMismatch:



Public Member Functions

- std::string description () const override
 - Exception description.
- Exception (const std::string &where)

Constructs an exception.

7.73.1 Detailed Description

Type mismatch exception.

Scalar types do not match

7.73.2 Member Function Documentation

7.73.2.1 description()

std::string qpp::exception::TypeMismatch::description () const [inline], [override], [virtual]
Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.73.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


• classes/exception.h

7.74 qpp::exception::UndefinedType Class Reference


Not defined for this type exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception:: Undefined Type:$



Collaboration diagram for qpp::exception::UndefinedType:



Public Member Functions

- std::string description () const override
 - Exception description.
- Exception (const std::string &where)

Constructs an exception.

7.74.1 Detailed Description

Not defined for this type exception.

Templated specialization is not defined for this type

7.74.2 Member Function Documentation

7.74.2.1 description()

std::string qpp::exception::UndefinedType::description () const [inline], [override], [virtual]
Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.74.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


• classes/exception.h

7.75 qpp::exception::Unknown Class Reference


Unknown exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Unknown:



Collaboration diagram for qpp::exception::Unknown:



Public Member Functions

- std::string description () const override
 - Exception description.
- Exception (const std::string &where)

Constructs an exception.

7.75.1 Detailed Description

Unknown exception.

Thrown when no other exception is suitable (not recommended, it is better to define another suitable exception type)

7.75.2 Member Function Documentation

7.75.2.1 description()

std::string qpp::exception::Unknown::description () const [inline], [override], [virtual]
Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.75.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--


The documentation for this class was generated from the following file:

· classes/exception.h


7.76 qpp::QCircuit::iterator::value_type_ Class Reference

Value type class for qpp::QCircuit::iterator.

Inheritance diagram for qpp::QCircuit::iterator::value_type_:



Collaboration diagram for qpp::QCircuit::iterator::value_type_:



Public Member Functions

```
    value_type_ (const QCircuit *value_type_qc)
        Default value_type_ constructor.
    value_type_ (const value_type_ &)=default
        Default copy constructor.
    value_type_ & operator= (const value_type_ &)=default
        Default copy assignment operator.
```

Public Attributes

```
    const QCircuit * value_type_qc_
        < non-owning pointer to the grand-parent const quantum circuit</li>
    StepType type_{StepType::NONE}
        step type
    idx ip_{static_cast<idx>(-1)}
        instruction pointer
    std::vector< GateStep >::const_iterator gates_ip_{gates instruction pointer}
    std::vector< MeasureStep >::const_iterator measurements_ip_{measurements instruction pointer}
```

Private Member Functions

7.76.1 Detailed Description

Value type class for qpp::QCircuit::iterator.

7.76.2 Constructor & Destructor Documentation

Parameters

value_type_qc	Pointer to constant quantum circuit
---------------	-------------------------------------

Default copy constructor.

7.76.3 Member Function Documentation

7.76.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream the textual representation of the iterator de-referenced element

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.76.3.2 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

7.76.4 Member Data Documentation

```
7.76.4.1 gates_ip_
std::vector<GateStep>::const_iterator qpp::QCircuit::iterator::value_type_::gates_ip_ {}
gates instruction pointer
7.76.4.2 ip_
idx qpp::QCircuit::iterator::value_type_::ip_ {static_cast<idx>(-1)}
instruction pointer
7.76.4.3 measurements_ip_
\verb|std::vector<| \texttt{MeasureStep}>::const_iterator | qpp::QCircuit::iterator::value_type_::measurements\_{\leftarrow}| to the const_iterator | to the const_itera
measurements instruction pointer
7.76.4.4 type_
StepType qpp::QCircuit::iterator::value_type_::type_ {StepType::NONE}
step type
7.76.4.5 value_type_qc_
const QCircuit* qpp::QCircuit::iterator::value_type_::value_type_qc_
 < non-owning pointer to the grand-parent const quantum circuit
The documentation for this class was generated from the following file:
```


• classes/circuits/circuits.h

7.77 qpp::exception::ZeroSize Class Reference


Object has zero size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::ZeroSize:



Collaboration diagram for qpp::exception::ZeroSize:



360 Class Documentation

Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.77.1 Detailed Description

Object has zero size exception.

Zero sized object, e.g. empty Eigen::Matrix or std::vector with no elements

7.77.2 Member Function Documentation

7.77.2.1 description()

```
std::string qpp::exception::ZeroSize::description ( ) const [inline], [override], [virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.77.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where T	Text representing where the exception occurred
---------	--

The documentation for this class was generated from the following file:

· classes/exception.h


Chapter 8

File Documentation

8.1 classes/circuits/circuits.h File Reference

Qudit quantum circuits.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::QCircuit

Quantum circuit class.

• struct qpp::QCircuit::GateStep

One step consisting only of gates/operators in the circuit.

• struct qpp::QCircuit::MeasureStep

One step consisting only of measurements in the circuit.

· class qpp::QCircuit::iterator

Quantum circuit bound-checking (safe) iterator.

• class qpp::QCircuit::iterator::value_type_

Value type class for qpp::QCircuit::iterator.

Namespaces

• qpp

Quantum++ main namespace.


8.1.1 Detailed Description

Qudit quantum circuits.

8.2 classes/circuits/engines.h File Reference

Qudit quantum engines.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::QEngine

Quantum circuit engine, executes qpp::QCircuit.

class qpp::QNoisyEngine < NoiseModel >

Noisy quantum circuit engine, executes qpp::QCircuit.

Namespaces

• qpp

Quantum++ main namespace.


8.2.1 Detailed Description

Qudit quantum engines.

8.3 classes/codes.h File Reference

Quantum error correcting codes.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::Codes

const Singleton class that defines quantum error correcting codes

Namespaces

qpp

Quantum++ main namespace.

8.3.1 Detailed Description

Quantum error correcting codes.

8.4 classes/exception.h File Reference

Exceptions.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::exception::Exception

Base class for generating Quantum++ custom exceptions.

· class qpp::exception::Unknown

Unknown exception.

class qpp::exception::ZeroSize

Object has zero size exception.

class gpp::exception::MatrixNotSquare

Matrix is not square exception.

· class qpp::exception::MatrixNotCvector

Matrix is not a column vector exception.

class qpp::exception::MatrixNotRvector

Matrix is not a row vector exception.

class qpp::exception::MatrixNotVector

Matrix is not a vector exception.

class qpp::exception::MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

• class qpp::exception::MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

class qpp::exception::MatrixNotSquareNorVector

Matrix is not square nor vector exception.

class qpp::exception::MatrixMismatchSubsys

Matrix mismatch subsystems exception.

· class qpp::exception::DimsInvalid

Invalid dimension(s) exception.

· class qpp::exception::DimsNotEqual

Dimensions not equal exception.

class qpp::exception::DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

class qpp::exception::DimsMismatchCvector

Dimension(s) mismatch column vector size exception.

class qpp::exception::DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

class qpp::exception::DimsMismatchVector

Dimension(s) mismatch vector size exception.

class qpp::exception::SubsysMismatchDims

Subsystems mismatch dimensions exception.

• class qpp::exception::PermInvalid

Invalid permutation exception.

· class qpp::exception::PermMismatchDims

Permutation mismatch dimensions exception.

class qpp::exception::NotQubitMatrix

Matrix is not 2 x 2 exception.

· class qpp::exception::NotQubitCvector

Column vector is not 2 x 1 exception.

class qpp::exception::NotQubitRvector

Row vector is not 1 x 2 exception.

class qpp::exception::NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

class qpp::exception::NotQubitSubsys

Subsystems are not qubits exception.

· class qpp::exception::NotBipartite

Not bi-partite exception.

· class qpp::exception::NoCodeword

Codeword does not exist exception.

class qpp::exception::OutOfRange

Argument out of range exception.

class qpp::exception::TypeMismatch

Type mismatch exception.

• class qpp::exception::SizeMismatch

Size mismatch exception.

class qpp::exception::UndefinedType

Not defined for this type exception.

• class qpp::exception::QuditAlreadyMeasured

Qudit was already measured exception.

• class qpp::exception::Duplicates

System (e.g. std::vector) has duplicates exception.

class qpp::exception::CustomException

Custom exception.

· class qpp::exception::NotImplemented

Code not yet implemented.

· class qpp::exception::InvalidIterator

Invalid iterator.

Namespaces

• qpp

Quantum++ main namespace.

• qpp::exception

Quantum++ exception hierarchy namespace.


8.4.1 Detailed Description

Exceptions.

8.5 classes/gates.h File Reference

Quantum gates.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::Gates

const Singleton class that implements most commonly used gates

Namespaces

• qpp

Quantum++ main namespace.


8.5.1 Detailed Description

Quantum gates.

8.6 classes/idisplay.h File Reference

Display interface via the non-virtual interface (NVI) and very basic JSON serialization support interface.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

· class qpp::IJSON

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

Namespaces

• qpp

Quantum++ main namespace.


8.6.1 Detailed Description

Display interface via the non-virtual interface (NVI) and very basic JSON serialization support interface.

8.7 classes/init.h File Reference

Initialization.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::Init

const Singleton class that performs additional initializations/cleanups

Namespaces

• qpp

Quantum++ main namespace.


8.7.1 Detailed Description

Initialization.

8.8 classes/noise.h File Reference

Noise models.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::NoiseType

Contains template tags used to specify the noise type.

class qpp::NoiseBase< T >

Base class for all noise models, derive your particular noise model.

• class qpp::QubitDepolarizingNoise

Qubit depolarizing noise.

• class qpp::QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

• class qpp::QubitBitFlipNoise

Qubit bit flip noise.

· class qpp::QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

• class qpp::QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

• class qpp::QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

· class qpp::QuditDepolarizingNoise

Qudit depolarizing noise.

Namespaces

• qpp

Quantum++ main namespace.


8.8.1 Detailed Description

Noise models.

8.9 classes/random_devices.h File Reference

Random devices.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::RandomDevices

Singleton class that manages the source of randomness in the library.

Namespaces

qpp

Quantum++ main namespace.


8.9.1 Detailed Description

Random devices.

8.10 classes/reversible.h File Reference

Support for classical reversible circuits.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::Dynamic_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime.

class qpp::Bit_circuit

Classical reversible circuit simulator.

Namespaces

• qpp

Quantum++ main namespace.


8.10.1 Detailed Description

Support for classical reversible circuits.

8.11 classes/states.h File Reference

Quantum states.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::States

const Singleton class that implements most commonly used states

Namespaces

qpp

Quantum++ main namespace.

8.11.1 Detailed Description

Quantum states.

8.12 classes/timer.h File Reference

Timing.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::Timer < T, CLOCK_T >
 Chronometer.

Namespaces

• qpp

Quantum++ main namespace.


8.12.1 Detailed Description

Timing.

8.13 constants.h File Reference

Constants.

This graph shows which files directly or indirectly include this file:



Namespaces

- qpp
 - Quantum++ main namespace.
- qpp::literals

Functions

- constexpr cplx qpp::literals::operator"" _i (unsigned long long int x) noexcept
 - User-defined literal for complex $i = \sqrt{-1}$ (integer overload)
- constexpr cplx qpp::operator"" _i (long double x) noexcept
 - User-defined literal for complex $i = \sqrt{-1}$ (real overload)
- cplx qpp::omega (idx D)
 - D-th root of unity.

Variables

- constexpr double qpp::chop = 1e-10
 - Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.
- constexpr idx qpp::maxn = 64
 - Maximum number of allowed qubits/qudits (subsystems)
- constexpr double qpp::pi = 3.141592653589793238462643383279502884
 - π
- constexpr double qpp::ee = 2.718281828459045235360287471352662497
 - Base of natural logarithm, e.
- constexpr double qpp::infty = std::numeric_limits<double>::max()
 - Used to denote infinity in double precision.


8.13.1 Detailed Description

Constants.

8.14 entanglement.h File Reference

Entanglement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Schmidt basis on Bob side.

Functions

```
    template<typename Derived >
        dyn_col_vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector<
        idx > &dims)
```

Schmidt coefficients of the bi-partite pure state A.

```
    template<typename Derived >
        dyn_col_vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2)

    Schmidt coefficients of the bi-partite pure state A.
```

template<typename Derived >
 cmat qpp::schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
 Schmidt basis on Alice side.

template < typename Derived >
 cmat qpp::schmidtA (const Eigen::MatrixBase < Derived > &A, idx d=2)
 Schmidt basis on Alice side.

 $\begin{tabular}{ll} & \textbf{template}$< typename Derived > \\ & \textbf{cmat qpp::schmidtB} (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &dims) \\ \end{tabular}$

template<typename Derived >
 cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2)

Schmidt basis on Bob side.

template<typename Derived >
 std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx
 > &dims)

Schmidt probabilities of the bi-partite pure state A.

• template<typename Derived >

std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)

Schmidt probabilities of the bi-partite pure state A.

• template<typename Derived >

double qpp::entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)

Entanglement of the bi-partite pure state A.

• template<typename Derived >

double qpp::entanglement (const Eigen::MatrixBase< Derived > &A, idx d=2)

Entanglement of the bi-partite pure state A.

• template<typename Derived >

double qpp::gconcurrence (const Eigen::MatrixBase Derived > &A)

G-concurrence of the bi-partite pure state A.

• template<typename Derived >

double qpp::negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)

Negativity of the bi-partite mixed state A.

template < typename Derived >

double qpp::negativity (const Eigen::MatrixBase< Derived > &A, idx d=2)

Negativity of the bi-partite mixed state A.

ullet template<typename Derived >

double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)

Logarithmic negativity of the bi-partite mixed state A.

• template<typename Derived >

double qpp::lognegativity (const Eigen::MatrixBase Derived > &A, idx d=2)

Logarithmic negativity of the bi-partite mixed state A.

• template<typename Derived >

double qpp::concurrence (const Eigen::MatrixBase Derived > &A)

Wootters concurrence of the bi-partite qubit mixed state A.


8.14.1 Detailed Description

Entanglement functions.

8.15 entropies.h File Reference

Entropy functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 double qpp::entropy (const Eigen::MatrixBase< Derived > &A)

von-Neumann entropy of the density matrix A

double qpp::entropy (const std::vector< double > &prob)

Shannon entropy of the probability distribution prob.

• template<typename Derived >

double qpp::renyi (const Eigen::MatrixBase Derived > &A, double alpha)

Renyi- α entropy of the density matrix A, for $\alpha \geq 0$.

double qpp::renyi (const std::vector< double > &prob, double alpha)

Renyi- α entropy of the probability distribution prob, for $\alpha \geq 0$.

 $\bullet \ \ {\sf template}{<} {\sf typename \ Derived} >$

double qpp::tsallis (const Eigen::MatrixBase< Derived > &A, double q)

Tsallis- q entropy of the density matrix A, for $q \ge 0$.

double qpp::tsallis (const std::vector< double > &prob, double q)

Tsallis- q entropy of the probability distribution prob, for $q \geq 0$.

• template<typename Derived >

double qpp::qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const std::vector< idx > &subsysB, const std::vector< idx > &dims)

Quantum mutual information between 2 subsystems of a composite system.

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

double qpp::qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const std::vector< idx > &subsysB, idx d=2)

Quantum mutual information between 2 subsystems of a composite system.

8.15.1 Detailed Description

Entropy functions.

8.16 experimental/experimental.h File Reference

Experimental/test functions/classes.

Namespaces

• qpp

Quantum++ main namespace.

· qpp::experimental

Experimental/test functions/classes, do not use or modify.


8.16.1 Detailed Description

Experimental/test functions/classes.

8.17 functions.h File Reference

Generic quantum computing functions.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::internal::HashEigen

Functor for hashing Eigen expressions.

• class qpp::internal::EqualEigen

Functor for comparing Eigen expressions for equality.

Namespaces

• qpp

Quantum++ main namespace.

- · qpp::literals
- qpp::internal

Internal utility functions, do not use them directly or modify them.

Functions

```
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::transpose (const Eigen::MatrixBase< Derived > &A)
• template<typename Derived >
  dyn mat< typename Derived::Scalar > qpp::conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::adjoint (const Eigen::MatrixBase< Derived > &A)
      Adjoint.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::inverse (const Eigen::MatrixBase< Derived > &A)
      Inverse.

    template<typename Derived >

  Derived::Scalar qpp::trace (const Eigen::MatrixBase < Derived > &A)
• template<typename Derived >
  Derived::Scalar <a href="mailto:qpp::det">qpp::det</a> (const Eigen::MatrixBase</a> Derived > &A)

    template<typename Derived >

  Derived::Scalar qpp::logdet (const Eigen::MatrixBase< Derived > &A)
     Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar <a href="mailto:qpp::sum">qpp::sum</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise sum of A.
template<typename Derived >
  Derived::Scalar <a href="mailto:open:prod">open:prod</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise product of A.

    template<typename Derived >

  double <a href="mailto:qpp::norm">qpp::norm</a> (const Eigen::MatrixBase< Derived > &A)
      Frobenius norm.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::normalize (const Eigen::MatrixBase< Derived > &A)
      Normalizes state vector (column or row vector) or density matrix.
• template<typename Derived >
  std::pair< dyn_col_vect< cplx >, cmat > qpp::eig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition.
• template<typename Derived >
  dyn_col_vect< cplx > qpp::evals (const Eigen::MatrixBase< Derived > &A)
     Eigenvalues.

    template<typename Derived >

  cmat qpp::evects (const Eigen::MatrixBase< Derived > &A)
      Eigenvectors.

    template<typename Derived >

  std::pair< dyn_col_vect< double >, cmat > qpp::heig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > qpp::hevals (const Eigen::MatrixBase< Derived > &A)
      Hermitian eigenvalues.
• template<typename Derived >
  cmat qpp::hevects (const Eigen::MatrixBase< Derived > &A)
      Eigenvectors of Hermitian matrix.
```

```
• template<typename Derived >
  std::tuple< cmat, dyn_col_vect< double >, cmat > qpp::svd (const Eigen::MatrixBase< Derived > &A)
     Full singular value decomposition.

    template<typename Derived >

  dyn_col_vect< double > qpp::svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.
• template<typename Derived >
  cmat qpp::svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.

    template<typename Derived >

  cmat qpp::svdV (const Eigen::MatrixBase< Derived > &A)
     Right singular vectors.

    template<typename Derived >

  cmat qpp::funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)

    template<typename Derived >

  cmat qpp::sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.
• template<typename Derived >
  cmat qpp::absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.

    template<typename Derived >

  cmat qpp::expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.

    template<typename Derived >

  cmat qpp::logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.

    template<typename Derived >

  cmat <a href="mailto:qpp::sinm">qpp::sinm</a> (const Eigen::MatrixBase</a> Derived > &A)
     Matrix sin.
• template<typename Derived >
  cmat qpp::cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.
• template<typename Derived >
  cmat qpp::spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::powm (const Eigen::MatrixBase< Derived > &A, idx n)
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

    template<typename Derived >

  double qpp::schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > qpp::cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const
  typename Derived::Scalar &))
     Functor.
• template<typename T >
  dyn mat< typename T::Scalar > qpp::kron (const T &head)
     Kronecker product.
template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > qpp::kron (const T &head, const Args &... tail)
     Kronecker product.
```

```
    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::kron (const std::vector< Derived > &As)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::kron (const std::initializer_list< Derived > &As)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
      Kronecker power.

    template<typename T >

  dyn_mat< typename T::Scalar > qpp::dirsum (const T &head)
      Direct sum.
• template<typename T , typename... Args>
  dyn mat< typename T::Scalar > qpp::dirsum (const T &head, const Args &... tail)
      Direct sum.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::vector< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::initializer_list< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::reshape (const Eigen::MatrixBase< Derived > &A, idx rows,
  idx cols)
     Reshape.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > qpp::comm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
      Commutator.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > qpp::anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::prj (const Eigen::MatrixBase< Derived > &A)
     Projector.

    template<typename Derived >

  \label{lem:dyn_mat} \textit{dyn\_mat} < \textit{typename Derived::} \textit{Scalar} > \textit{qpp::} \textit{grams} \; (\textit{const std::} \textit{vector} < \textit{Derived} > \& \textit{As})
     Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::grams (const std::initializer list< Derived > &As)
      Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::grams (const Eigen::MatrixBase< Derived > &A)
     Gram-Schmidt orthogonalization.

    std::vector< idx > qpp::n2multiidx (idx n, const std::vector< idx > &dims)

     Non-negative integer index to multi-index.

    idx qpp::multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

     Multi-index to non-negative integer index.

    ket qpp::mket (const std::vector< idx > &mask, const std::vector< idx > &dims)
```

Multi-partite qudit ket.

ket qpp::mket (const std::vector< idx > &mask, idx d=2)

Multi-partite qudit ket. cmat qpp::mprj (const std::vector < idx > &mask, const std::vector < idx > &dims) Projector onto multi-partite qudit ket. cmat qpp::mprj (const std::vector< idx > &mask, idx d=2) Projector onto multi-partite qudit ket. • template<typename InputIterator > std::vector< double > qpp::abssq (InputIterator first, InputIterator last) Computes the absolute values squared of an STL-like range of complex numbers. template<typename Container > std::vector< double > qpp::abssq (const Container &c, typename std::enable if< is iterable< Container >::value >::type *=nullptr) Computes the absolute values squared of an STL-like container. template<typename Derived > std::vector< double > qpp::abssq (const Eigen::MatrixBase< Derived > &A) Computes the absolute values squared of an Eigen expression. • template<typename InputIterator > std::iterator_traits < InputIterator >::value_type qpp::sum (InputIterator first, InputIterator last) Element-wise sum of an STL-like range. template<typename Container > Container::value_type qpp::sum (const Container &c, typename std::enable_if< is_iterable< Container >← ::value >::type *=nullptr) Element-wise sum of the elements of an STL-like container. template<typename InputIterator > std::iterator_traits< InputIterator >::value_type qpp::prod (InputIterator first, InputIterator last) Element-wise product of an STL-like range. template<typename Container > Container::value type qpp::prod (const Container &c, typename std::enable if < is iterable < Container >← ::value >::type *=nullptr) Element-wise product of the elements of an STL-like container. template<typename Derived > dyn_col_vect< typename Derived::Scalar > qpp::rho2pure (const Eigen::MatrixBase< Derived > &A) Finds the pure state representation of a matrix proportional to a projector onto a pure state. std::vector< idx > qpp::complement (std::vector< idx > subsys, idx n) Constructs the complement of a subsystem vector. template<typename Derived > std::vector< double > qpp::rho2bloch (const Eigen::MatrixBase< Derived > &A) Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A. cmat qpp::bloch2rho (const std::vector< double > &r) Computes the density matrix corresponding to the 3-dimensional real Bloch vector r. • template<char... Bits> ket qpp::literals::operator"" _ket () Multi-partite qubit ket user-defined literal. • template<char... Bits> bra qpp::literals::operator"" _bra () Multi-partite qubit bra user-defined literal. • template<char... Bits> cmat qpp::literals::operator"" _prj () Multi-partite qubit projector user-defined literal. template < class T > void qpp::internal::hash combine (std::size t &seed, const T &v) template<typename Derived > std::size_t qpp::hash_eigen (const Eigen::MatrixBase< Derived > &A, std::size_t seed=0) Computes the hash of en Eigen matrix/vector/expression.


8.17.1 Detailed Description

Generic quantum computing functions.

8.18 input output.h File Reference

Input/output functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 internal::IOManipEigen qpp::disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
 Eigen expression ostream manipulator.

internal::IOManipEigen qpp::disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

• template<typename InputIterator >

internal::IOManipRange< InputIterator > qpp::disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")

Range ostream manipulator.

• template<typename Container >

internal::IOManipRange< typename Container::const_iterator > qpp::disp (const Container &c, const std⇔ ::string &separator, const std::string &start="[", const std::string &end="]", typename std::enable_if< is_⇔ iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

• template<typename PointerType >

internal::IOManipPointer< PointerType > qpp::disp (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")

C-style pointer ostream manipulator.

• template<typename Derived >

void qpp::save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.


8.18.1 Detailed Description

Input/output functions.

8.19 instruments.h File Reference

Measurement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)
 Generalized inner product.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

ullet template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >
 std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase
 Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

• template<typename Derived >

std::tuple < idx, std::vector < double >, std::vector < cmat > > qpp::measure (const Eigen::MatrixBase < Derived > &A, const std::vector < cmat > &Ks, const std::vector < idx > &target, const std::vector < idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template < typename Derived >

 $std::tuple < idx, std::vector < double >, std::vector < cmat > > qpp::measure (const Eigen::MatrixBase < Derived > &A, const std::initializer_list < cmat > &Ks, const std::vector < idx > &target, const std::vector < idx > &dims)$

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > qpp::measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

• template<typename Derived >

 $std::tuple < std::vector < idx >, double, cmat > qpp::measure_seq (const Eigen::MatrixBase < Derived > \&A, std::vector < idx > target, idx d=2)$

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.


8.19.1 Detailed Description

Measurement functions.

8.20 internal/classes/iomanip.h File Reference

Input/output manipulators.

This graph shows which files directly or indirectly include this file:



Classes

- class qpp::internal::IOManipRange< InputIterator >
- class qpp::internal::IOManipPointer< PointerType >
- class qpp::internal::IOManipEigen

Namespaces

• qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


8.20.1 Detailed Description

Input/output manipulators.

8.21 internal/classes/singleton.h File Reference

Singleton pattern via CRTP.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::internal::Singleton< T >

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Namespaces

• qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


8.21.1 Detailed Description

Singleton pattern via CRTP.

8.22 internal/util.h File Reference

Internal utility functions.

This graph shows which files directly or indirectly include this file:



Classes

struct qpp::internal::Display_Impl_

Namespaces

qpp

Quantum++ main namespace.

· qpp::internal

Internal utility functions, do not use them directly or modify them.

Functions

- void qpp::internal::n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx qpp::internal::multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- ullet template<typename Derived >

bool qpp::internal::check square mat (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

bool qpp::internal::check_vector (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_rvector (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_cvector (const Eigen::MatrixBase< Derived > &A)

template<typename T >

bool qpp::internal::check_nonzero_size (const T &x) noexcept

• template<typename T1 , typename T2 >

bool app::internal::check matching sizes (const T1 &lhs, const T2 &rhs) noexcept

- bool qpp::internal::check dims (const std::vector < idx > &dims)
- template<typename Derived >

bool qpp::internal::check_dims_match_mat (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_dims_match_cvect (const std::vector < idx > &dims, const Eigen::MatrixBase < Derived > &A)

template<typename Derived >

bool qpp::internal::check_dims_match_rvect (const std::vector < idx > &dims, const Eigen::MatrixBase < Derived > &A)

- bool qpp::internal::check eq dims (const std::vector < idx > &dims, idx dim) noexcept
- bool app::internal::check no duplicates (std::vector< idx > v)
- bool qpp::internal::check_subsys_match_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)
- $\bullet \ \ {\it template}{<} {\it typename Derived} >$

bool qpp::internal::check_qubit_matrix (const Eigen::MatrixBase< Derived > &A) noexcept

• template<typename Derived >

bool qpp::internal::check_qubit_cvector (const Eigen::MatrixBase< Derived > &A) noexcept

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

 $bool\ qpp::internal::check_qubit_rvector\ (const\ Eigen::MatrixBase < Derived > \&A)\ noexcept$

• template<typename Derived >

bool qpp::internal::check_qubit_vector (const Eigen::MatrixBase< Derived > &A) noexcept

- bool qpp::internal::check_perm (const std::vector< idx > &perm)
- template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::internal::kron2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::MatrixBase< Derived2 > &B)

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::internal::dirsum2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::MatrixBase< Derived2 > &B)

• template<typename T >

void qpp::internal::variadic_vector_emplace (std::vector< T > &)

- template<typename T , typename First , typename... Args>
 - $\label{eq:condition} \mbox{void qpp::internal::variadic_vector_emplace} \mbox{ (std::vector< $T > \&v$, First \&\&first, Args \&\&... args) } \\$
- idx qpp::internal::get_num_subsys (idx D, idx d)
- idx qpp::internal::get_dim_subsys (idx sz, idx N)

8.22.1 Detailed Description

Internal utility functions.

8.23 MATLAB/matlab.h File Reference

Input/output interfacing with MATLAB.

```
#include "mat.h"
#include "mex.h"
```

Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< cplx > ::type
 qpp::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::

Scalar > >::type qpp::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >
 std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.


8.23.1 Detailed Description

Input/output interfacing with MATLAB.

8.24 number_theory.h File Reference

Number theory functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

std::vector< int > qpp::x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

• double qpp::contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

• bigint qpp::gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint qpp::gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint qpp::lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint qpp::lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > qpp::invperm (const std::vector< idx > &perm)

Inverse permutation.

• std::vector< idx > qpp::compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

std::vector< bigint > qpp::factors (bigint a)

Prime factor decomposition.

• bigint qpp::modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

• bigint qpp::modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple < bigint, bigint, bigint > qpp::egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint qpp::modinv (bigint a, bigint p)

Modular inverse of a mod p.

bool qpp::isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

• bigint qpp::randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

- std::vector< std::pair< int, int > > qpp::convergents (const std::vector< int > &cf)
 Convergents.
- std::vector< std::pair< int, int > > qpp::convergents (double x, idx N)
 Convergents.


8.24.1 Detailed Description

Number theory functions.

8.25 operations.h File Reference

Quantum operation functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 const std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 idx d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived >

```
cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)
```

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std \leftrightarrow ::vector< idx > &target, const std::vector< idx > &dims)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std
::vector< idx > &target, idx d=2)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat qpp::kraus2super (const std::vector< cmat > &Ks)

Superoperator matrix.

cmat qpp::kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector< cmat > qpp::choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat qpp::choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat qpp::super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

Partial trace.

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

dyn_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

• template<typename Derived >

 $\label{lem:dyn_mat} $$ dyn_mat< typename\ Derived::Scalar > qpp::ptrace2\ (const\ Eigen::MatrixBase<\ Derived > \&A,\ const\ std $$::vector< idx > \&dims)$$

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

 $\bullet \ \ {\sf template}{<} {\sf typename \ Derived}>$

Partial trace.

 $\bullet \ \ \mathsf{template}{<}\mathsf{typename} \ \mathsf{Derived}>$

dyn_mat< typename Derived::Scalar > qpp::ptrace (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Partial transpose.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2)

Partial transpose.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &perm, const std::vector< idx > &dims)

Subsystem permutation.

• template<typename Derived >

 $dyn_mat < typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &perm, idx d=2)$

Subsystem permutation.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::applyQFT (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::applyTFQ (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

dyn_col_vect< typename Derived::Scalar > qpp::TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

• template<typename Derived >

 $\label{local_vect} $$ dyn_col_vect< typename \ Derived::Scalar > qpp::QFT \ (const \ Eigen::MatrixBase< \ Derived > \&A, \ idx \ d=2, \ bool \ swap=true) $$$

Qudit quantum Fourier transform.

8.25.1 Detailed Description

Quantum operation functions.

8.26 qpp.h File Reference

Quantum++ main header file, includes all other necessary headers.

```
#include <algorithm>
#include <cassert>
#include <chrono>
#include <cmath>
#include <complex>
#include <cstdlib>
#include <cstring>
#include <exception>
#include <fstream>
```

```
#include <functional>
#include <initializer list>
#include <iomanip>
#include <iterator>
#include <limits>
#include <memory>
#include <numeric>
#include <ostream>
#include <random>
#include <sstream>
#include <stdexcept>
#include <string>
#include <tuple>
#include <type_traits>
#include <unordered_map>
#include <utility>
#include <vector>
#include <Eigen/Dense>
#include <Eigen/SVD>
#include "types.h"
#include "classes/exception.h"
#include "constants.h"
#include "traits.h"
#include "classes/idisplay.h"
#include "internal/util.h"
#include "internal/classes/iomanip.h"
#include "input_output.h"
#include "internal/classes/singleton.h"
#include "classes/random_devices.h"
#include "random.h"
#include "number_theory.h"
#include "functions.h"
#include "classes/init.h"
#include "classes/codes.h"
#include "classes/gates.h"
#include "classes/states.h"
#include "statistics.h"
#include "operations.h"
#include "entropies.h"
#include "entanglement.h"
#include "classes/timer.h"
#include "instruments.h"
#include "classes/reversible.h"
#include "classes/noise.h"
#include "classes/circuits/circuits.h"
#include "classes/circuits/engines.h"
```

Namespaces

• qpp

Quantum++ main namespace.

Macros

#define QPP_UNUSED_

8.26.1 Detailed Description

Quantum++ main header file, includes all other necessary headers.

8.26.2 Macro Definition Documentation


8.26.2.1 QPP_UNUSED_

#define QPP_UNUSED_

8.27 random.h File Reference

Randomness-related functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

double qpp::rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

• bigint qpp::rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx qpp::randidx (idx a=std::numeric_limits< idx >::min(), idx b=std::numeric_limits< idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

template<typename Derived >

Derived qpp::rand (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double a QPP_UNUSED_=0, double b QPP_UNUSED_=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

template<>

dmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

template<>

cmat gpp::rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived qpp::randn (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double mean QPP_UNUSED_=0, double sigma QPP_UNUSED_=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

dmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

template<>

cmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

• double qpp::randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

cmat qpp::randU (idx D=2)

Generates a random unitary matrix.

• cmat qpp::randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > qpp::randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat qpp::randH (idx D=2)

Generates a random Hermitian matrix.

ket qpp::randket (idx D=2)

Generates a random normalized ket (pure state vector)

• cmat qpp::randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > qpp::randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > qpp::randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.


8.27.1 Detailed Description

Randomness-related functions.

8.28 statistics.h File Reference

Statistics functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

std::vector< double > qpp::uniform (idx N)

Uniform probability distribution vector.

std::vector< double > qpp::marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > qpp::marginalY (const dmat &probXY)

Marginal distribution.

template<typename Container >
 double qpp::avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_←
 iterable< Container >::value >::type *=nullptr)

Average.

• template<typename Container >

 $\label{local-continuous} \begin{tabular}{ll} double & qpp::cov & (const & probXY, const & Container & X, const & Container & Y, typename & std::enable_if < is_iterable < Container >::value >::type *=nullptr) \\ \end{tabular}$

Covariance.

template<typename Container >
 double qpp::var (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_←
 iterable< Container >::value >::type *=nullptr)

Variance.

396 File Documentation

template<typename Container >
 double qpp::sigma (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_
 iterable< Container >::value >::type *=nullptr)

Standard deviation.

template<typename Container >
 double qpp::cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if<
 is_iterable< Container >::value >::type *=nullptr)
 Correlation.


8.28.1 Detailed Description

Statistics functions.

8.29 traits.h File Reference

Type traits.

This graph shows which files directly or indirectly include this file:



Classes

- struct qpp::make_void < Ts >
 - Helper for qpp::to_void<>> alias template.
- struct qpp::is_iterable < T, typename >
 - Checks whether T is compatible with an STL-like iterable container.
- struct qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(*(std::declval < T >().end()), decltype(*(std::declval < T >().end()))
 - Checks whether T is compatible with an STL-like iterable container, specialization for STL-like iterable containers.
- struct qpp::is_matrix_expression< Derived >
 - Checks whether the type is an Eigen matrix expression.
- struct qpp::is_complex< T >
 - Checks whether the type is a complex type.
- struct qpp::is_complex< std::complex< T >>
 - Checks whether the type is a complex number type, specialization for complex types.

Namespaces

• qpp

Quantum++ main namespace.

Typedefs

template < typename... Ts>
 using qpp::to_void = typename make_void < Ts... >::type
 Alias template that implements the proposal for void_t.


8.29.1 Detailed Description

Type traits.

8.30 types.h File Reference

Type aliases.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

398 File Documentation

Typedefs

• using qpp::idx = std::size_t

```
Non-negative integer index, make sure you use an unsigned type.
• using qpp::bigint = long long int
     Big integer.
using qpp::cplx = std::complex < double >
      Complex number in double precision.
• using qpp::ket = Eigen::VectorXcd
      Complex (double precision) dynamic Eigen column vector.
• using qpp::bra = Eigen::RowVectorXcd
      Complex (double precision) dynamic Eigen row vector.
• using qpp::cmat = Eigen::MatrixXcd
      Complex (double precision) dynamic Eigen matrix.
• using qpp::dmat = Eigen::MatrixXd
      Real (double precision) dynamic Eigen matrix.
• template<typename Scalar >
  using <a href="mailto:qpp::dyn_mat">qpp::dyn_mat</a> = Eigen::Matrix< Scalar, Eigen::Dynamic, Eigen::Dynamic >
      Dynamic Eigen matrix over the field specified by Scalar.
• template<typename Scalar >
  using qpp::dyn_col_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 >
      Dynamic Eigen column vector over the field specified by Scalar.
• template<typename Scalar >
  using qpp::dyn row vect = Eigen::Matrix < Scalar, 1, Eigen::Dynamic >
     Dynamic Eigen row vector over the field specified by Scalar.
```

8.30.1 Detailed Description

Type aliases.

Index

Dia sinsuia	05
~Bit_circuit	qpp, 35
qpp::Bit_circuit, 132	applyTFQ
~Codes	qpp, 36
qpp::Codes, 139	avg
~Dynamic_bitset	qpp, 36
qpp::Dynamic_bitset, 161	h00
~Gates	b00
qpp::Gates, 176	qpp::States, 338
~IDisplay	b01
qpp::IDisplay, 190	qpp::States, 339
~IJSON	b10
qpp::IJSON, 192	qpp::States, 339
\sim Init	b11
qpp::Init, 194	qpp::States, 339
\sim NoiseBase	bCNOT_
qpp::NoiseBase, 241	qpp::Bit_circuit, 136
\sim QCircuit	bFRED_
qpp::QCircuit, 273	qpp::Bit_circuit, 136
\sim QEngine	bNOT_
qpp::QEngine, 299	qpp::Bit_circuit, 136
\sim RandomDevices	bSWAP_
qpp::RandomDevices, 326	qpp::Bit_circuit, 136
\sim Singleton	bTOF_
qpp::internal::Singleton, 330	qpp::Bit_circuit, 136
~States	begin
qpp::States, 336	qpp::QCircuit, 274
~Timer	bigint
qpp::Timer, 346	qpp, 26
	Bit_circuit
A_	gpp::Bit circuit, 131
qpp::internal::IOManipEigen, 198	bloch2rho
absm	qpp, 36
qpp, 29	bra
abssq	qpp, 26
qpp, 29, 30	btotal
add hash	gpp::Bit circuit, 136
qpp::QCircuit, 273	φρε. <u>ι_</u> σποαιί, 100
adjoint	c_reg_
qpp, 30	qpp::QCircuit::MeasureStep, 235
all	cCTRL_custom
qpp::Dynamic_bitset, 161	qpp::QCircuit, 276
anticomm	cCTRL
qpp, 31	qpp::QCircuit, 274–276
	CNOTba
<pre>any qpp::Dynamic_bitset, 161</pre>	qpp::Gates, 183
apply	CNOT
qpp, 31–33	qpp::Bit_circuit, 132
applyCTRL	qpp::Gates, 183
qpp, 34 applyQFT	CTRL_custom app::QCircuit, 279
addival. I	addGCICUIL. 2/8

CTRL	classes/noise.h, 368
qpp::Gates, 176	classes/random_devices.h, 369
qpp::QCircuit, 277–279	classes/reversible.h, 369
cbegin	classes/states.h, 370
qpp::QCircuit, 274	classes/timer.h, 371
cend	cmat
qpp::QCircuit, 277	qpp, 27
check_cvector	cmat_hash_tbl_
qpp::internal, 120	qpp::QCircuit, 294
check_dims	Codes
qpp::internal, 120	qpp::Codes, 139 codeword
check_dims_match_cvect	qpp::Codes, 139
qpp::internal, 120	comm
check_dims_match_mat	qpp, 38
qpp::internal, 120	complement
check_dims_match_rvect	qpp, 38
qpp::internal, 120	compperm
check_eq_dims	qpp, 39
qpp::internal, 121	compute probs
check_matching_sizes	qpp::NoiseBase, 241
qpp::internal, 121	compute state
check_no_duplicates qpp::internal, 121	qpp::NoiseBase, 241
	concurrence
check_nonzero_size	qpp, 39
qpp::internal, 121	conjugate
check_perm	qpp, 40
qpp::internal, 121 check_qubit_cvector	const_iterator
qpp::internal, 121	qpp::QCircuit, 271
check_qubit_matrix	constants.h, 372
qpp::internal, 122	contfrac2x
check_qubit_rvector	qpp, 40
qpp::internal, 122	convergents
check_qubit_vector	qpp, 40, 41
app::internal, 122	cor
check rvector	qpp, 41
qpp::internal, 122	cosm
check_square_mat	qpp, 42
qpp::internal, 122	count
check subsys match dims	qpp::Dynamic_bitset, 161
qpp::internal, 122	count_
check_vector	qpp::Bit_circuit, 136
qpp::internal, 123	qpp::QCircuit, 294
choi2kraus	COV
qpp, 37	qpp, 42
choi2super	cplx
qpp, 37	qpp, 27
chop	ctrl_
qpp, 116	qpp::QCircuit::GateStep, 187
chop_	CustomException
qpp::internal::IOManipEigen, 198	qpp::exception::CustomException, 141
classes/circuits/circuits.h, 361	cwise
classes/circuits/engines.h, 362	qpp, 43 CZ
classes/codes.h, 363	qpp::Gates, 184
classes/exception.h, 363	ηρρααισο, 10 4
classes/gates.h, 365	d_
classes/idisplay.h, 366	qpp::NoiseBase, 245
classes/init.h, 367	qpp::QCircuit, 294
	

data	qpp::QEngine, 299
qpp::Dynamic_bitset, 161	qpp::Timer, 347
depth_	qpp::internal::IOManipEigen, 198
qpp::Bit_circuit, 137	qpp::internal::IOManipPointer, 200
description	qpp::internal::IOManipRange, 204
qpp::exception::CustomException, 142	display_impl_
qpp::exception::DimsInvalid, 144	qpp::internal::Display_Impl_, 155
qpp::exception::DimsMismatchCvector, 146	dits_
qpp::exception::DimsMismatchMatrix, 148	qpp::QEngine, 306
qpp::exception::DimsMismatchRvector, 150	dmat
qpp::exception::DimsMismatchVector, 152	qpp, 27
qpp::exception::DimsNotEqual, 154	dyn_col_vect
qpp::exception::Duplicates, 157	qpp, 27
qpp::exception::Exception, 172	dyn_mat
qpp::exception::InvalidIterator, 196	qpp, 27
qpp::exception::MatrixMismatchSubsys, 218	dyn_row_vect
qpp::exception::MatrixNotCvector, 221	qpp, 28
qpp::exception::MatrixNotRvector, 223	Dynamic_bitset
qpp::exception::MatrixNotSquare, 225	qpp::Dynamic_bitset, 160
qpp::exception::MatrixNotSquareNorCvector, 227	20
qpp::exception::MatrixNotSquareNorRvector, 229	ee ann 116
qpp::exception::MatrixNotSquareNorVector, 231	qpp, 116
qpp::exception::MatrixNotVector, 233	egcd
qpp::exception::NoCodeword, 237	qpp, 48 eig
qpp::exception::NotBipartite, 248	qpp, 49
qpp::exception::NotImplemented, 250	elem
qpp::exception::NotQubitCvector, 252	qpp::QCircuit::iterator, 216
qpp::exception::NotQubitMatrix, 254	end
qpp::exception::NotQubitRvector, 256	qpp::QCircuit, 280
qpp::exception::NotQubitSubsys, 258	end_
qpp::exception::NotQubitVector, 260	qpp::Timer, 348
qpp::exception::OutOfRange, 262	qpp::internal::IOManipPointer, 201
qpp::exception::PermInvalid, 264	qpp::internal::IOManipRange, 204
qpp::exception::PermMismatchDims, 266	entanglement
qpp::exception::QuditAlreadyMeasured, 321	qpp, 49, 50
qpp::exception::SizeMismatch, 332	entanglement.h, 373
qpp::exception::SubsysMismatchDims, 344	entropies.h, 374
qpp::exception::TypeMismatch, 350	entropy
qpp::exception::UndefinedType, 352	qpp, 50, 51
qpp::exception::Unknown, 354	evals
qpp::exception::ZeroSize, 360	qpp, 51
det	evects
qpp, 43	qpp, 51
difference_type	Exception
qpp::QCircuit::iterator, 212	qpp::exception::DimsInvalid, 144
dirsum	qpp::exception::DimsMismatchCvector, 146
qpp, 44, 45	qpp::exception::DimsMismatchMatrix, 148
dirsum2	qpp::exception::DimsMismatchRvector, 150
qpp::internal, 123	qpp::exception::DimsMismatchVector, 152
dirsumpow	qpp::exception::DimsNotEqual, 154
qpp, 45	qpp::exception::Duplicates, 157
disp	qpp::exception::Exception, 172
qpp, 46–48	qpp::exception::InvalidIterator, 196
display	qpp::exception::MatrixMismatchSubsys, 219
qpp::Dynamic_bitset, 162	qpp::exception::MatrixNotCvector, 221
qpp::IDisplay, 190	qpp::exception::MatrixNotRvector, 223
qpp::QCircuit, 280	qpp::exception::MatrixNotSquare, 225
qpp::QCircuit::iterator::value_type_, 357	qpp::exception::MatrixNotSquareNorCvector, 227

qpp::exception::MatrixNotSquareNorRvector, 229	gate_type_
qpp::exception::MatrixNotSquareNorVector, 231	qpp::QCircuit::GateStep, 188
qpp::exception::MatrixNotVector, 233	GateStep
qpp::exception::NoCodeword, 237	qpp::QCircuit::GateStep, 187
qpp::exception::NotBipartite, 248	GateType
qpp::exception::NotImplemented, 250	qpp::QCircuit, 271
qpp::exception::NotQubitCvector, 252	Gates
qpp::exception::NotQubitMatrix, 254	qpp::Gates, 176
qpp::exception::NotQubitRvector, 256	gates_
qpp::exception::NotQubitSubsys, 258	qpp::QCircuit, 294
qpp::exception::NotQubitVector, 260	gates_ip_
qpp::exception::OutOfRange, 262	<pre>qpp::QCircuit::iterator::value_type_, 357</pre>
qpp::exception::PermInvalid, 264	gcd
qpp::exception::PermMismatchDims, 266	qpp, 53
qpp::exception::QuditAlreadyMeasured, 322	gconcurrence
qpp::exception::SizeMismatch, 332	qpp, 54
qpp::exception::SubsysMismatchDims, 344	generated_
qpp::exception::TypeMismatch, 350	qpp::NoiseBase, 245
qpp::exception::UndefinedType, 352	get
qpp::exception::Unknown, 354	qpp::Dynamic_bitset, 163
qpp::exception::ZeroSize, 360	get_Ks
execute	qpp::NoiseBase, 242
qpp::QEngine, 300	get_circuit
qpp::QNoisyEngine, 309, 310	qpp::QEngine, 300
expandout	get_cmat_hash_tbl_
qpp::Gates, 177, 178	qpp::QCircuit, 283
experimental/experimental.h, 376	
expm	get_d
qpp, 52	qpp::NoiseBase, 242
H 1 7	qpp::QCircuit, 283
FRED	get_dim_subsys
qpp::Bit_circuit, 132	qpp::internal, 123
qpp::Gates, 184	get_dit
factors	qpp::QEngine, 301
qpp, 52	get_dits
Fd	qpp::QEngine, 301
qpp::Gates, 179	get_duration
fill_Ks_	qpp::Timer, 347
qpp::QuditDepolarizingNoise, 324	get_gate_count
fill_probs_	qpp::Bit_circuit, 133
qpp::QuditDepolarizingNoise, 324	qpp::QCircuit, 284
first	get_gate_depth
qpp::internal::IOManipRange, 205	qpp::Bit_circuit, 133
flip	qpp::QCircuit, 284
qpp::Dynamic_bitset, 162	get_gates_
functions.h, 376	qpp::QCircuit, 285
funm	get_instance
qpp, 53	qpp::internal::Singleton, 330
۹۳۲, ۵۵	get_last_idx
GHZ	qpp::NoiseBase, 242
qpp::States, 339	get_last_K
gate	qpp::NoiseBase, 243
qpp::QCircuit, 280, 281	get_last_p
gate custom	qpp::NoiseBase, 243
qpp::QCircuit, 282	get_measured
gate_fan	qpp::QCircuit, 285
qpp::QCircuit, 282, 283	qpp::QEngine, 301, 302
gate_hash_	get_measurement_count
qpp::QCircuit::GateStep, 187	qpp::QCircuit, 285, 286

get_measurements_	idx
qpp::QCircuit, 286	qpp, 28
get_name	index_
qpp::Gates, 179	qpp::Dynamic_bitset, 163
qpp::QCircuit, 286	infty
get_nc	qpp, 116
qpp::QCircuit, 286	Init
get_noise_results	qpp::Init, 194
qpp::QNoisyEngine, 310	input_output.h, 381
get_non_measured	instruments.h, 382
gpp::QCircuit, 287	internal/classes/iomanip.h, 383
qpp::QEngine, 302	internal/classes/singleton.h, 384
get nop count	internal/util.h, 385
qpp::QCircuit, 287	internal::Singleton< const Codes >
get_nq gnn::OCircuit 297	qpp::Codes, 139
qpp::QCircuit, 287	internal::Singleton< const Gates >
get_num_subsys	qpp::Gates, 183
qpp::internal, 123	internal::Singleton< const Init >
get_prng	qpp::Init, 194
qpp::RandomDevices, 327	internal::Singleton< const States >
get_probs	qpp::States, 338
qpp::NoiseBase, 243	internal::Singleton < RandomDevices >
qpp::QEngine, 302	qpp::RandomDevices, 328
get psi	inverse
qpp::QEngine, 302	qpp, 57
get_relative_pos_	invperm
qpp::QEngine, 303	qpp, 58
get_step_count	
qpp::QCircuit, 287	ip
	qpp, 58, 59
get_thread_local_instance	ip_
qpp::internal::Singleton, 330	qpp::QCircuit::iterator::value_type_, 358
grams	isprime
qpp, 54, 55	qpp, 59
	iterator
Н	qpp::QCircuit::iterator, 213
qpp::Gates, 184	iterator_category
hash_combine	qpp::QCircuit::iterator, 212
qpp::internal, 123	
hash_eigen	jn
qpp, 56	qpp::States, 336
heig	11 /
qpp, 56	ket
hevals	qpp, 28
qpp, 57	kraus2choi
hevects	qpp, 59
qpp, 57	kraus2super
:	qpp, 60
I_	kron
qpp::NoiseBase, 245	qpp, 60–62
IOManipEigen	kron2
qpp::internal::IOManipEigen, 198	qpp::internal, 123
IOManipPointer	kronpow
qpp::internal::IOManipPointer, 200	qpp, 62
IOManipRange	Ks_
qpp::internal::IOManipRange, 203, 204	
ld	qpp::NoiseBase, 245
	qppivoisebase, 245
qpp::Gates, 179	last_
qpp::Gates, 179	last_

qpp, 63	qpp, 78
load	msg_
qpp, 64	qpp::exception::Exception, 173
qpp::RandomDevices, 327	multiidx2n
loadMATLAB	qpp, 79
qpp, 64, 65	qpp::internal, 124
logdet	
qpp, 66	n2multiidx
. "	qpp, 79
logm	
qpp, 66	qpp::internal, 124
lognegativity	N_
qpp, 67	qpp::internal::IOManipPointer, 201
• • •	n
MATLAB/matlab.h, 387	qpp::Dynamic_bitset, 168
MODMUL	
	NOT
qpp::Gates, 180	qpp::Bit_circuit, 134
marginalX	name_
qpp, 67	qpp::QCircuit, 295
marginalY	qpp::QCircuit::GateStep, 188
-	
qpp, 69	qpp::QCircuit::MeasureStep, 235
mats_hash_	nc_
qpp::QCircuit::MeasureStep, 235	qpp::QCircuit, 295
maxn	negativity
qpp, 116	
	qpp, 80
measure	noise_
qpp, 69–74	qpp::QNoisyEngine, 310
measure_seq	noise_results_
qpp, 74, 75	qpp::QNoisyEngine, 311
MeasureStep	
	noise_type
qpp::QCircuit::MeasureStep, 234, 235	qpp::NoiseBase, 240
MeasureType	NoiseBase
qpp::QCircuit, 272	qpp::NoiseBase, 240
measured_	none
qpp::QCircuit, 294	qpp::Dynamic_bitset, 163
measurement_count_	nop
qpp::QCircuit, 295	qpp::QCircuit, 289
measurement_type_	norm
qpp::QCircuit::MeasureStep, 235	
	qpp, 81
measurements_	normalize
qpp::QCircuit, 295	qpp, 81
measurements_ip_	nq
qpp::QCircuit::iterator::value_type_, 358	qpp::QCircuit, 295
measureV	** *
	number_theory.h, 387
qpp::QCircuit, 288	
measureZ	offset_
qpp::QCircuit, 289	qpp::Dynamic_bitset, 164
mes	omega
	_
qpp::States, 336	qpp, 82
minus	one
qpp::States, 337	qpp::States, 337
mket	operations.h, 389
qpp, 75, 76	operator!=
modinv	qpp::Dynamic_bitset, 164
qpp, 76	qpp::QCircuit::iterator, 213
modmul	operator<<
qpp, 77	qpp::IDisplay, 191
	qpp::QCircuit, 292, 293
modpow	
qpp, 77	operator*
mprj	qpp::QCircuit::iterator, 214

operator()	ptrace
qpp::NoiseBase, 243, 244	qpp, 84, 85
qpp::internal::EqualEigen, 169	ptrace1
qpp::internal::HashEigen, 189	qpp, 85, 86
operator++	ptrace2
qpp::QCircuit::iterator, 214	qpp, 86, 87
operator-	ptranspose
qpp::Dynamic_bitset, 164	qpp, 87, 88
operator=	pW
qpp::QCircuit::iterator, 214	qpp::States, 340
<pre>qpp::QCircuit::iterator::value_type_, 357</pre>	px0
qpp::QEngine, 303	qpp::States, 340
qpp::internal::IOManipPointer, 201	px1
qpp::internal::IOManipRange, 204	qpp::States, 340
qpp::internal::Singleton, 330	py0
operator==	qpp::States, 341
qpp::Dynamic_bitset, 165	py1
qpp::QCircuit::iterator, 215	qpp::States, 341
operator"" _bra	pz0
qpp::literals, 125	qpp::States, 341
operator""_i	pz1
qpp, 82	qpp::States, 341
qpp::literals, 125	-11-1-
operator"" _ket	QCircuit
qpp::literals, 126	qpp::QCircuit, 273
operator"" _prj	QEngine
qpp::literals, 126	qpp::QCircuit, 294
apptorais, 120	qpp::QEngine, 298, 299
p_	QFT
qpp::internal::IOManipPointer, 201	qpp, <mark>88</mark>
pGHZ	qpp::QCircuit, 289, 290
qpp::States, 340	QNoisyEngine
pb00	qpp::QNoisyEngine, 309
qpp::States, 339	QPP UNUSED
pb01	qpp.h, 393
qpp::States, 339	qc_
pb10	qpp::QCircuit::iterator, 216
qpp::States, 340	qpp::QEngine, 306
pb11	qmutualinfo
qpp::States, 340	qpp, 89
pi	qpp, 13
qpp, 116	absm, 29
plus	abssq, 29, 30
qpp::States, 337	adjoint, 30
pointer	anticomm, 31
qpp::QCircuit::iterator, 212	apply, 31–33
powm	applyCTRL, 34
qpp, 82	applyQFT, 35
prj	applyTFQ, 36
qpp, 83	avg, 36
prng_	bigint, 26
qpp::RandomDevices, 328	bloch2rho, 36
probs	bra, 26
qpp::NoiseBase, 245	choi2kraus, 37
qpp::QEngine, 306	choi2super, 37
	chop, 116
prod	
qpp, 83, 84	cmat, 27
psi_ app::OEngine_306	comm, 38
qpp::QEngine, 306	complement, 38

compperm, 39	modinv, 76
concurrence, 39	modmul, 77
conjugate, 40	modpow, 77
contfrac2x, 40	mprj, 78
convergents, 40, 41	multiidx2n, 79
cor, 41	n2multiidx, 79
cosm, 42	negativity, 80
cov, 42	norm, 81
cplx, 27	normalize, 81
cwise, 43	omega, <mark>82</mark>
det, 43	operator"" _i, 82
dirsum, 44, 45	pi, 116
dirsumpow, 45	powm, 82
disp, 46–48	prj, 83
dmat, 27	prod, 83, 84
dyn_col_vect, 27	ptrace, 84, 85
dyn_mat, 27	ptrace1, 85, 86
dyn_row_vect, 28	ptrace2, 86, 87
ee, 116	ptranspose, 87, 88
egcd, 48	QFT, 88
eig, 49	qmutualinfo, 89
entanglement, 49, 50	rand, 90-92
entropy, 50, 51	randH, 92
evals, 51	randidx, 93
evects, 51	randket, 93
expm, 52	randkraus, 93
factors, 52	randn, 94, 95
funm, 53	randperm, 96
gcd, 53	randprime, 96
gconcurrence, 54	randprob, 97
grams, 54, 55	randrho, 97
hash eigen, 56	randU, 97
heig, 56	randV, 98
hevals, 57	renyi, 98, 99
hevects, 57	reshape, 99
idx, 28	rho2bloch, 100
infty, 116	rho2pure, 100
inverse, 57	save, 101
invperm, 58	saveMATLAB, 101, 102
ip, 58, 59	schatten, 102
isprime, 59	schmidtA, 103
ket, 28	schmidtB, 103, 104
kraus2choi, 59	schmidtcoeffs, 104, 105
kraus2super, 60	schmidtprobs, 105, 106
kron, 60–62	sigma, 106
kronpow, 62	sinm, 107
Icm, 63	spectralpowm, 107
load, 64	sqrtm, 108
loadMATLAB, 64, 65	sum, 108, 109
	Jann, 100, 100
loadet 66	
logdet, 66	super2choi, 109
logm, 66	super2choi, 109 svals, 110
logm, 66 lognegativity, 67	super2choi, 109 svals, 110 svd, 110
logm, 66 lognegativity, 67 marginalX, 67	super2choi, 109 svals, 110 svd, 110 svdU, 110
logm, 66 lognegativity, 67 marginalX, 67 marginalY, 69	super2choi, 109 svals, 110 svd, 110 svdU, 110 svdV, 111
logm, 66 lognegativity, 67 marginalX, 67 marginalY, 69 maxn, 116	super2choi, 109 svals, 110 svd, 110 svdU, 110 svdV, 111 syspermute, 111, 112
logm, 66 lognegativity, 67 marginalX, 67 marginalY, 69 maxn, 116 measure, 69–74	super2choi, 109 svals, 110 svd, 110 svdU, 110 svdV, 111 syspermute, 111, 112 TFQ, 112
logm, 66 lognegativity, 67 marginalX, 67 marginalY, 69 maxn, 116	super2choi, 109 svals, 110 svd, 110 svdU, 110 svdV, 111 syspermute, 111, 112

transpose, 113	v_, 168
tsallis, 113, 114	value_type, 160
uniform, 114	qpp::Gates, 173
var, 115	\sim Gates, 176
x2contfrac, 115	CNOTba, 183
qpp.h, 391	CNOT, 183
QPP_UNUSED_, 393	CTRL, 176
qpp::Bit_circuit, 129	CZ, 184
\sim Bit_circuit, 132	expandout, 177, 178
bCNOT_, 136	FRED, 184
bFRED_, 136	Fd, 179
bNOT_, 136	Gates, 176
bSWAP_, 136	get_name, 179
bTOF_, 136	H, 184
Bit_circuit, 131	ld, 179
btotal_, 136	ld2, 184
CNOT, 132	internal::Singleton < const Gates >, 183
count_, 136	MODMUL, 180
depth_, 137	Rn, 180
FRED, 132	RX, 181
get_gate_count, 133	RY, 181
get_gate_depth, 133	RZ, 182
NOT, 134	S, 184
reset, 134	SWAPd, 182
SWAP, 134	SWAP, 184
TOF, 135	T, 185
X, 135	TOF, 185
qpp::Codes, 137	X, 185
~Codes, 139	Xd, 182 V 195
Codes, 139	Y, 185
codeword, 139	Z, 185
internal::Singleton< const Codes >, 139	Zd, 183
Type, 138	qpp::IDisplay, 189
qpp::Dynamic_bitset, 157	∼IDisplay, 190
~Dynamic_bitset, 161	display, 190
all, 161	operator<<, 191
any, 161	qpp::IJSON, 191
count, 161	∼IJSON, 192
data, 161	to_JSON, 192
display, 162	qpp::Init, 192
Dynamic_bitset, 160	\sim Init, 194
flip, 162	Init, 194
get, 163	internal::Singleton< const Init >, 194
index_, 163	qpp::NoiseBase
n_, 168	\sim NoiseBase, 241
none, 163	compute_probs_, 241
offset_, 164	compute_state_, 241
operator!=, 164	d_, 245
operator-, 164	generated_, 245
operator==, 165	get_Ks, 242
rand, 165, 166	get_d, 242
reset, 166	get_last_idx, 242
set, 166, 167	get_last_K, 243
size, 167	get_last_p, 243
storage_size, 167	get_probs, 243
storage_size_, 168	i_, 245
storage_type, 160	Ks_, 245
to_string, 167	noise_type, 240
	71 /

NoiseBase, 240	TFQ, 290, 291
operator(), 243, 244	to_JSON, 292
probs_, 245	qpp::QCircuit::GateStep, 186
qpp::NoiseBase< T >, 238	ctrl_, 187
qpp::NoiseType, 246	gate_hash_, 187
qpp::NoiseType::StateDependent, 333	gate_type_, 188
qpp::NoiseType::StateIndependent, 333	GateStep, 187
qpp::QCircuit, 267	name_, 188
∼QCircuit, 273	target_, 188
add_hash_, 273	qpp::QCircuit::MeasureStep, 233
begin, 274	c_reg_, 235
cCTRL_custom, 276	mats_hash_, 235
cCTRL, 274–276	MeasureStep, 234, 235
CTRL_custom, 279	measurement_type_, 235
CTRL, 277–279	name_, 235
cbegin, 274	target_, 236
cend, 277	qpp::QCircuit::iterator, 211
cmat_hash_tbl_, 294	difference_type, 212
const_iterator, 271	elem_, 216
count_, 294	iterator, 213
d_, 294	iterator_category, 212
display, 280	operator!=, 213
end, 280	operator*, 214
gate, 280, 281	operator++, 214
gate_custom, 282	operator=, 214
gate_fan, 282, 283	operator==, 215
GateType, 271	pointer, 212
gates_, 294	qc_, 216
get_cmat_hash_tbl_, 283	reference, 213
get_d, 283	set_begin_, 215
get_gate_count, 284	set_end_, 215
get_gate_depth, 284	value_type, 213
get_gates_, 285	qpp::QCircuit::iterator::value_type_, 355
get_measured, 285	display, 357
get_measurement_count, 285, 286	gates_ip_, 357
get_measurements_, 286	ip_, 358
get_name, 286	measurements_ip_, 358
get_nc, 286	operator=, 357
get_non_measured, 287	type_, 358
get_nop_count, 287	value_type_, 356, 357
get_nq, 287 get step count, 287	value_type_qc_, 358
MeasureType, 272	qpp::QEngine, 296 ∼QEngine, 299
measured , 294	•
_	display, 299
measurement_count_, 295	dits_, 306
measureN 295	execute, 300
measureV, 288 measureZ, 289	get_circuit, 300 get_dit, 301
name_, 295	get_dits, 301 get_measured, 301, 302
nc_, 295 nop, 289	get_non_measured, 302
ng_, 295	get_probs, 302
operator<<, 292, 293	get_probs, 302 get_psi, 302
QCircuit, 273	get_relative_pos_, 303
QEngine, 294	operator=, 303
QFT, 289, 290	probs_, 306
step_types_, 295	psi_, 306
StepTypes_, 293 StepType, 272	QEngine, 298, 299
0.001,000, 2.12	GENGINO, 200, 200

qc_, 306	px0, 340
reset, 303	px1, 340
set_dit, 303	py0, 341
set_measured_, 305	py1, 341
set_psi, 305	pz0, 341
subsys_, 307	pz1, 341
to_JSON, 305	States, 336
qpp::QNoisyEngine	W, 341
execute, 309, 310	x0, 341
get_noise_results, 310	x1, 342
noise_, 310	y0, 342
noise_results_, 311	y1, 342
QNoisyEngine, 309	z0, 342
qpp::QNoisyEngine < NoiseModel >, 307	z1, 342
qpp::QubitAmplitudeDampingNoise, 311	zero, 338
QubitAmplitudeDampingNoise, 312	qpp::Timer
qpp::QubitBitFlipNoise, 313	\sim Timer, 346
QubitBitFlipNoise, 314	display, 347
qpp::QubitBitPhaseFlipNoise, 314	end_, 348
QubitBitPhaseFlipNoise, 315	get_duration, 347
qpp::QubitDepolarizingNoise, 316	start_, <mark>348</mark>
QubitDepolarizingNoise, 317	tic, 347
qpp::QubitPhaseDampingNoise, 317	tics, 348
QubitPhaseDampingNoise, 318	Timer, 346
qpp::QubitPhaseFlipNoise, 319	toc, 348
QubitPhaseFlipNoise, 320	qpp::Timer< T, CLOCK_T >, 345
qpp::QuditDepolarizingNoise, 322	qpp::exception, 116
fill_Ks_, 324	qpp::exception::CustomException, 140
fill_probs_, 324	CustomException, 141
QuditDepolarizingNoise, 323	description, 142
qpp::RandomDevices, 325	what_, 142
\sim RandomDevices, 326	qpp::exception::DimsInvalid, 143
get_prng, 327	description, 144
internal::Singleton< RandomDevices >, 328	Exception, 144
load, 327	qpp::exception::DimsMismatchCvector, 145
prng_, 328	description, 146
RandomDevices, 326	Exception, 146
rd_, 328	qpp::exception::DimsMismatchMatrix, 147
save, 327	description, 148
qpp::States, 333	Exception, 148
\sim States, 336	qpp::exception::DimsMismatchRvector, 149
b00, 338	description, 150
b01, 339	Exception, 150
b10, 339	qpp::exception::DimsMismatchVector, 151
b11, 339	description, 152
GHZ, 339	Exception, 152
internal::Singleton $<$ const States $>$, 338	qpp::exception::DimsNotEqual, 153
jn, 336	description, 154
mes, 336	Exception, 154
minus, 337	qpp::exception::Duplicates, 156
one, 337	description, 157
pGHZ, 340	Exception, 157
pb00, 339	qpp::exception::Exception, 170
pb01, 339	description, 172
pb10, 340	Exception, 172
pb11, 340	msg_, 173
plus, 337	what, 172
pW, 340	where_, 173

qpp::exception::InvalidIterator, 194	description, 266
description, 196	Exception, 266
Exception, 196	qpp::exception::QuditAlreadyMeasured, 320
qpp::exception::MatrixMismatchSubsys, 217	description, 321
description, 218	Exception, 322
Exception, 219	qpp::exception::SizeMismatch, 331
qpp::exception::MatrixNotCvector, 219	description, 332
description, 221	Exception, 332
Exception, 221	qpp::exception::SubsysMismatchDims, 343
qpp::exception::MatrixNotRvector, 221	description, 344
description, 223	Exception, 344
Exception, 223	qpp::exception::TypeMismatch, 349
qpp::exception::MatrixNotSquare, 223	description, 350
description, 225	Exception, 350
Exception, 225	qpp::exception::UndefinedType, 351
qpp::exception::MatrixNotSquareNorCvector, 225	description, 352
description, 227	Exception, 352
Exception, 227	app::exception::Unknown, 353
qpp::exception::MatrixNotSquareNorRvector, 227	description, 354
description, 229	Exception, 354
Exception, 229	qpp::exception::ZeroSize, 359
qpp::exception::MatrixNotSquareNorVector, 229	description, 360
description, 231	Exception, 360
Exception, 231	qpp::experimental, 118
qpp::exception::MatrixNotVector, 231	qpp::internal, 118
description, 233	check_cvector, 120
Exception, 233	check_dims, 120
qpp::exception::NoCodeword, 236	check_dims_match_cvect, 120
description, 237	check_dims_match_mat, 120
Exception, 237	check_dims_match_rvect, 120
qpp::exception::NotBipartite, 246	check_eq_dims, 121
description, 248	check_matching_sizes, 121
Exception, 248	check_no_duplicates, 121
qpp::exception::NotImplemented, 248	check_nonzero_size, 121
description, 250	check_perm, 121
Exception, 250	check_qubit_cvector, 121
qpp::exception::NotQubitCvector, 250	check_qubit_matrix, 122
description, 252	check qubit rvector, 122
Exception, 252	check_qubit_vector, 122
qpp::exception::NotQubitMatrix, 252	check_rvector, 122
description, 254	check_square_mat, 122
Exception, 254	check_subsys_match_dims, 122
•	check_vector, 123
qpp::exception::NotQubitRvector, 254	
description, 256	dirsum2, 123
Exception, 256	get_dim_subsys, 123
qpp::exception::NotQubitSubsys, 256	get_num_subsys, 123
description, 258	hash_combine, 123
Exception, 258	kron2, 123
qpp::exception::NotQubitVector, 258	multiidx2n, 124
description, 260	n2multiidx, 124
Exception, 260	variadic_vector_emplace, 124
qpp::exception::OutOfRange, 260	qpp::internal::Display_Impl_, 155
description, 262	display_impl_, 155
Exception, 262	qpp::internal::EqualEigen, 169
qpp::exception::PermInvalid, 262	operator(), 169
description, 264	qpp::internal::HashEigen, 188
Exception, 264	operator(), 189
qpp::exception::PermMismatchDims, 264	qpp::internal::IOManipEigen, 196

A_, 198	qpp::QubitPhaseFlipNoise, 320
chop_, 198	QuditDepolarizingNoise
display, 198	qpp::QuditDepolarizingNoise, 323
IOManipEigen, 198	qppQualibepolarizing(10130, 020
qpp::internal::IOManipPointer	rand
display, 200	qpp, 90–92
end_, 201	qpp::Dynamic_bitset, 165, 166
IOManipPointer, 200	randH
N , 201	qpp, 92
operator=, 201	randidx
p_, 201	qpp, 93
separator_, 201	randket
start_, 202	qpp, 93
qpp::internal::IOManipPointer< PointerType >, 199	randkraus
qpp::internal::IOManipRange	qpp, 93
display, 204	randn
end_, 204	qpp, 94, 95
first_, 205	random.h, 393
IOManipRange, 203, 204	RandomDevices
last , 205	qpp::RandomDevices, 326
operator=, 204	randperm
separator_, 205	qpp, 96
start_, 205	randprime
qpp::internal::IOManipRange< InputIterator >, 202	qpp, 96
app::internal::Singleton	randprob
~Singleton, 330	qpp, 97
get_instance, 330	randrho
get_thread_local_instance, 330	qpp, 97
operator=, 330	randU
Singleton, 329, 330	qpp, 97
qpp::internal::Singleton $<$ T $>$, 328	randV
qpp::is_complex< std::complex< T > >, 207	qpp, 98
qpp::is_complex< T >, 206	rd_
qpp::is_iterable< T, to_void< decltype(std::declval< T	qpp::RandomDevices, 328
$>$ ().begin()), decltype(std::declval $<$ T $>$ (). \leftarrow	reference
end()), decltype(*(std::declval< T >().←	qpp::QCircuit::iterator, 213
begin()))>>, 209	renyi
qpp::is_iterable< T, typename >, 208	qpp, 98, 99
qpp::is matrix expression< Derived >, 210	reset
qpp::literals, 125	qpp::Bit_circuit, 134
operator"" _bra, 125	qpp::Dynamic_bitset, 166 qpp::QEngine, 303
operator"" _i, 125	reshape
operator"" _i, 125 operator"" _ket, 126 operator"" _prj, 126	qpp, 99
operator"" _prj, 126	rho2bloch
qpp::make_void	qpp, 100
type, 217	rho2pure
qpp::make_void< Ts >, 216	qpp, 100
QubitAmplitudeDampingNoise	Rn
qpp::QubitAmplitudeDampingNoise, 312	qpp::Gates, 180
QubitBitFlipNoise	RX
qpp::QubitBitFlipNoise, 314	qpp::Gates, 181
QubitBitPhaseFlipNoise	RY
qpp::QubitBitPhaseFlipNoise, 315	qpp::Gates, 181
QubitDepolarizingNoise	RZ
qpp::QubitDepolarizingNoise, 317	qpp::Gates, 182
QubitPhaseDampingNoise	W-1
qpp::QubitPhaseDampingNoise, 318	S
QubitPhaseFlipNoise	qpp::Gates, 184

SWAPd	storage_size
qpp::Gates, 182	qpp::Dynamic_bitset, 167
SWAP	storage_size_
qpp::Bit_circuit, 134	qpp::Dynamic_bitset, 168
qpp::Gates, 184	storage_type
save	qpp::Dynamic_bitset, 160
qpp, 101	subsys_
qpp::RandomDevices, 327	qpp::QEngine, 307
saveMATLAB	sum
qpp, 101, 102	qpp, 108, 109
	super2choi
schatten	qpp, 109
qpp, 102	svals
schmidtA	
qpp, 103	qpp, 110
schmidtB	svd
qpp, 103, 104	qpp, 110
schmidtcoeffs	svdU
qpp, 104, 105	qpp, 110
schmidtprobs	svdV
qpp, 105, 106	qpp, 111
separator	syspermute
qpp::internal::IOManipPointer, 201	qpp, 111, 112
qpp::internal::IOManipRange, 205	
	Т
set	qpp::Gates, 185
qpp::Dynamic_bitset, 166, 167	TFQ
set_begin_	qpp, 112
qpp::QCircuit::iterator, 215	qpp::QCircuit, 290, 291
set_dit	TOF
qpp::QEngine, 303	
set_end_	qpp::Bit_circuit, 135
qpp::QCircuit::iterator, 215	qpp::Gates, 185
set measured	target_
	qpp::QCircuit::GateStep, 188
qpp::QEngine, 305	qpp::QCircuit::MeasureStep, 236
set_psi	tic
qpp::QEngine, 305	qpp::Timer, 347
sigma	tics
qpp, 106	qpp::Timer, 348
Singleton	Timer
qpp::internal::Singleton, 329, 330	qpp::Timer, 346
sinm	to JSON
qpp, 107	qpp::IJSON, 192
size	qpp::i00014, 102 qpp::QCircuit, 292
qpp::Dynamic_bitset, 167	
spectralpowm	qpp::QEngine, 305
	to_string
qpp, 107	qpp::Dynamic_bitset, 167
sqrtm	to_void
qpp, 108	qpp, <mark>28</mark>
start_	toc
qpp::Timer, 348	qpp::Timer, 348
qpp::internal::IOManipPointer, 202	trace
qpp::internal::IOManipRange, 205	qpp, 112
States	traits.h, 396
qpp::States, 336	transpose
statistics.h, 395	
	qpp, 113
step_types_	tsallis
qpp::QCircuit, 295	qpp, 113, 114
StepType	Туре
qpp::QCircuit, 272	qpp::Codes, 138

```
type
    qpp::make_void, 217
type_
    qpp::QCircuit::iterator::value_type_, 358
types.h, 397
uniform
    qpp, 114
    qpp::Dynamic_bitset, 168
value_type
    qpp::Dynamic_bitset, 160
    qpp::QCircuit::iterator, 213
value_type_
    qpp::QCircuit::iterator::value_type_, 356, 357
value_type_qc_
     qpp::QCircuit::iterator::value_type_, 358
var
     qpp, 115
variadic_vector_emplace
    qpp::internal, 124
W
    qpp::States, 341
what
    qpp::exception::Exception, 172
what
    qpp::exception::CustomException, 142
where_
    qpp::exception::Exception, 173
Χ
     qpp::Bit_circuit, 135
    qpp::Gates, 185
x0
    qpp::States, 341
х1
    qpp::States, 342
x2contfrac
     qpp, 115
Xd
    qpp::Gates, 182
Υ
    qpp::Gates, 185
y0
    qpp::States, 342
у1
    qpp::States, 342
Ζ
     qpp::Gates, 185
z0
    qpp::States, 342
z1
     qpp::States, 342
Zd
    qpp::Gates, 183
zero
     qpp::States, 338
```