Quantum++ v1.3

Generated by Doxygen 1.8.15

1 Quantum++	1
2 Namespace Index	3
2.1 Namespace List	3
3 Hierarchical Index	5
3.1 Class Hierarchy	5
4 Class Index	9
4.1 Class List	9
5 File Index	13
5.1 File List	13
6 Namespace Documentation	15
6.1 qpp Namespace Reference	15
6.1.1 Detailed Description	28
6.1.2 Typedef Documentation	28
6.1.2.1 bigint	28
6.1.2.2 bra	29
6.1.2.3 cmat	29
6.1.2.4 cplx	29
6.1.2.5 dmat	
6.1.2.6 dyn_col_vect	
6.1.2.7 dyn_mat	
6.1.2.8 dyn_row_vect	
6.1.2.9 idx	
6.1.2.10 ket	
6.1.2.11 to void	
6.1.3 Enumeration Type Documentation	
6.1.3.1 anonymous enum	
6.1.4 Function Documentation	
6.1.4.1 absm()	
6.1.4.2 abssq() [1/3]	
6.1.4.3 abssq() [2/3]	
6.1.4.4 abssq() [3/3]	
6.1.4.5 adjoint()	
6.1.4.6 anticomm()	
6.1.4.7 apply() [1/5]	
<b>6.1.4.8</b> apply() [2/5]	
<b>6.1.4.9</b> apply() [3/5]	
6.1.4.10 apply() [4/5]	
<b>6.1.4.11 apply()</b> [5/5]	
6.1.4.12 applyCTRL() [1/2]	36

6.1.4.13 applyCTRL() [2/2]
6.1.4.14 applyQFT()
6.1.4.15 applyTFQ()
6.1.4.16 avg()
6.1.4.17 bloch2rho()
6.1.4.18 choi2kraus()
6.1.4.19 choi2super()
6.1.4.20 comm()
6.1.4.21 complement()
6.1.4.22 compperm()
6.1.4.23 concurrence()
6.1.4.24 conjugate()
6.1.4.25 contfrac2x()
6.1.4.26 convergents() [1/2]
6.1.4.27 convergents() [2/2]
6.1.4.28 cor()
6.1.4.29 cosm()
6.1.4.30 cov()
6.1.4.31 cwise()
6.1.4.32 det()
6.1.4.33 dirsum() [1/4]
6.1.4.34 dirsum() [2/4]
6.1.4.35 dirsum() [3/4]
6.1.4.36 dirsum() [4/4]
6.1.4.37 dirsumpow()
6.1.4.38 disp() [1/5]
6.1.4.39 disp() [2/5]
6.1.4.40 disp() [3/5]
6.1.4.41 disp() [4/5]
6.1.4.42 disp() [5/5]
6.1.4.43 egcd()
6.1.4.44 eig()
6.1.4.45 entanglement() [1/2]
6.1.4.46 entanglement() [2/2] 52
6.1.4.47 entropy() [1/2]
6.1.4.48 entropy() [2/2]
6.1.4.49 evals()
6.1.4.50 evects()
6.1.4.51 expm()
6.1.4.52 factors()
6.1.4.53 funm()
6.1.4.54 gcd() [1/2]

<b>6.1.4.55 gcd()</b> [2/2]	55
6.1.4.56 gconcurrence()	56
<b>6.1.4.57 grams()</b> [1/3]	56
<b>6.1.4.58 grams()</b> [2/3]	57
<b>6.1.4.59 grams()</b> [3/3]	57
6.1.4.60 hash_eigen()	58
6.1.4.61 heig()	58
6.1.4.62 hevals()	59
6.1.4.63 hevects()	59
6.1.4.64 inverse()	59
6.1.4.65 invperm()	60
<b>6.1.4.66 ip()</b> [1/2]	60
<b>6.1.4.67 ip()</b> [2/2]	61
6.1.4.68 isprime()	61
6.1.4.69 kraus2choi()	61
6.1.4.70 kraus2super()	62
6.1.4.71 kron() [1/4]	62
<b>6.1.4.72 kron()</b> [2/4]	64
<b>6.1.4.73 kron()</b> [3/4]	64
6.1.4.74 kron() [4/4]	65
6.1.4.75 kronpow()	65
6.1.4.76 lcm() [1/2]	66
6.1.4.77 lcm() [2/2]	66
6.1.4.78 load()	67
<b>6.1.4.79 loadMATLAB()</b> [1/2]	67
<b>6.1.4.80 loadMATLAB()</b> [2/2]	68
6.1.4.81 logdet()	69
6.1.4.82 logm()	69
<b>6.1.4.83 lognegativity()</b> [1/2]	69
<b>6.1.4.84 lognegativity()</b> [2/2]	70
6.1.4.85 marginalX()	70
6.1.4.86 marginalY()	70
<b>6.1.4.87 measure()</b> [1/9]	71
<b>6.1.4.88 measure()</b> [2/9]	71
<b>6.1.4.89 measure()</b> [3/9]	72
<b>6.1.4.90 measure()</b> [4/9]	72
<b>6.1.4.91 measure()</b> [5/9]	73
<b>6.1.4.92 measure()</b> [6/9]	74
<b>6.1.4.93 measure()</b> [7/9]	74
<b>6.1.4.94 measure()</b> [8/9]	75
<b>6.1.4.95 measure()</b> [9/9]	76
6.1.4.96 measure_seq() [1/2]	76

6.1.4.97 measure_seq() [2/2]
6.1.4.98 mket() [1/2]
6.1.4.99 mket() [2/2]
6.1.4.100 modinv()
6.1.4.101 modmul()
6.1.4.102 modpow()
6.1.4.103 mprj() [1/2]
6.1.4.104 mprj() [2/2]
6.1.4.105 multiidx2n()
6.1.4.106 n2multiidx()
6.1.4.107 negativity() [1/2]
6.1.4.108 negativity() [2/2]
6.1.4.109 norm()
6.1.4.110 normalize()
6.1.4.111 omega()
6.1.4.112 powm()
6.1.4.113 prj()
6.1.4.114 prod() [1/3]
6.1.4.115 prod() [2/3]
6.1.4.116 prod() [3/3]
6.1.4.117 ptrace() [1/2]
6.1.4.118 ptrace() [2/2]
6.1.4.119 ptrace1() [1/2]
6.1.4.120 ptrace1() [2/2]
6.1.4.121 ptrace2() [1/2]
6.1.4.122 ptrace2() [2/2]
6.1.4.123 ptranspose() [1/2]
6.1.4.124 ptranspose() [2/2]
6.1.4.125 QFT()
6.1.4.126 qmutualinfo() [1/2] 9
6.1.4.127 qmutualinfo() [2/2] 9
6.1.4.128 rand() [1/5] 9
6.1.4.129 rand() [2/5] 9
6.1.4.130 rand() [3/5] 9
6.1.4.131 rand() [4/5] 9
6.1.4.132 rand() [5/5] 9
6.1.4.133 randH()
6.1.4.134 randidx()
6.1.4.135 randket()
6.1.4.136 randkraus()
6.1.4.137 randn() [1/4] 9
6.1.4.138 randn() [2/4]

6.1.4.139 randn() [3/4]
6.1.4.140 randn() [4/4]
6.1.4.141 randperm()
6.1.4.142 randprime()
6.1.4.143 randprob()
6.1.4.144 randrho()
6.1.4.145 randU()
6.1.4.146 randV()
6.1.4.147 renyi() [1/2]
6.1.4.148 renyi() [2/2]
6.1.4.149 reshape()
6.1.4.150 rho2bloch()
6.1.4.151 rho2pure()
6.1.4.152 save()
6.1.4.153 saveMATLAB() [1/2]
6.1.4.154 saveMATLAB() [2/2]
6.1.4.155 schatten()
6.1.4.156 schmidtA() [1/2]
6.1.4.157 schmidtA() [2/2]
6.1.4.158 schmidtB() [1/2]
6.1.4.159 schmidtB() [2/2]
6.1.4.160 schmidtcoeffs() [1/2]
6.1.4.161 schmidtcoeffs() [2/2]
6.1.4.162 schmidtprobs() [1/2]
6.1.4.163 schmidtprobs() [2/2]
6.1.4.164 sigma()
6.1.4.165 sinm()
6.1.4.166 spectralpowm()
6.1.4.167 sqrtm()
6.1.4.168 sum() [1/3]
6.1.4.169 sum() [2/3]
6.1.4.170 sum() [3/3]
6.1.4.171 super2choi()
6.1.4.172 svals()
6.1.4.173 svd()
6.1.4.174 svdU()
6.1.4.175 svdV()
6.1.4.176 syspermute() [1/2]
6.1.4.177 syspermute() [2/2]
6.1.4.178 TFQ()
6.1.4.179 trace()
6.1.4.180 transpose()

6.1.4.181 tsallis() [1/2]	115
6.1.4.182 tsallis() [2/2]	116
6.1.4.183 uniform()	116
6.1.4.184 var()	117
6.1.4.185 x2contfrac()	117
6.1.5 Variable Documentation	118
6.1.5.1 chop	118
6.1.5.2 ee	118
6.1.5.3 infty	118
6.1.5.4 maxn	118
6.1.5.5 pi	118
6.2 qpp::exception Namespace Reference	118
6.2.1 Detailed Description	120
6.3 qpp::experimental Namespace Reference	120
6.3.1 Detailed Description	120
6.4 qpp::internal Namespace Reference	120
6.4.1 Detailed Description	122
6.4.2 Function Documentation	122
6.4.2.1 abs_chop() [1/2]	122
6.4.2.2 abs_chop() [2/2]	122
6.4.2.3 check_cvector()	123
6.4.2.4 check_dims()	123
6.4.2.5 check_dims_match_cvect()	123
6.4.2.6 check_dims_match_mat()	123
6.4.2.7 check_dims_match_rvect()	123
6.4.2.8 check_eq_dims()	123
6.4.2.9 check_matching_sizes()	124
6.4.2.10 check_no_duplicates()	124
6.4.2.11 check_nonzero_size()	124
6.4.2.12 check_perm()	124
6.4.2.13 check_qubit_cvector()	124
6.4.2.14 check_qubit_matrix()	124
6.4.2.15 check_qubit_rvector()	125
6.4.2.16 check_qubit_vector()	125
6.4.2.17 check_rvector()	125
6.4.2.18 check_square_mat()	125
6.4.2.19 check_subsys_match_dims()	125
6.4.2.20 check_vector()	125
6.4.2.21 dirsum2()	126
6.4.2.22 get_dim_subsys()	126
6.4.2.23 get_num_subsys()	126
6.4.2.24 hash_combine()	126

6.4.2.25 kron2()	 126
6.4.2.26 multiidx2n()	 127
6.4.2.27 n2multiidx()	 127
6.4.2.28 variadic_vector_emplace() [1/2]	 127
<b>6.4.2.29</b> variadic_vector_emplace() [2/2]	 127
6.5 qpp::literals Namespace Reference	 128
6.5.1 Function Documentation	 128
6.5.1.1 operator""""_bra()	 128
6.5.1.2 operator"""i() [1/2]	 129
6.5.1.3 operator"""i() [2/2]	 129
6.5.1.4 operator"""if() [1/2]	 129
6.5.1.5 operator"""if() [2/2]	 129
6.5.1.6 operator""""_ket()	 129
6.5.1.7 operator""""_prj()	 130
	404
7 Class Documentation	131
7.1 qpp::Bit_circuit Class Reference	
7.1.1 Detailed Description	
7.1.2 Constructor & Destructor Documentation	
7.1.2.1 Bit_circuit() [1/2]	
7.1.2.2 Bit_circuit() [2/2]	
7.1.2.3 ~Bit_circuit()	
7.1.3 Member Function Documentation	
7.1.3.1 CNOT()	
7.1.3.2 FRED()	
7.1.3.3 get_gate_count()	
7.1.3.4 get_gate_depth()	
7.1.3.5 NOT()	
7.1.3.6 reset()	
7.1.3.7 SWAP()	
7.1.3.8 TOF()	
7.1.3.9 X()	
7.1.4 Member Data Documentation	
7.1.4.1 bCNOT	
7.1.4.2 bFRED	 138
7.1.4.3 bNOT	 138
7.1.4.4 bSWAP	 138
7.1.4.5 bTOF	 138
7.1.4.6 btotal	 138
7.1.4.7 count	 139
7.1.4.8 depth	 139
7.2 app.:Codes Class Reference	130

7.2.1 Detailed Description	-0
7.2.2 Member Enumeration Documentation	-0
7.2.2.1 Type	-C
7.2.3 Constructor & Destructor Documentation	-1
7.2.3.1 Codes()	-1
7.2.3.2 ~Codes()	-1
7.2.4 Member Function Documentation	-1
7.2.4.1 codeword()	-1
7.2.5 Friends And Related Function Documentation	-1
7.2.5.1 internal::Singleton < const Codes >	2
7.3 qpp::exception::CustomException Class Reference	2
7.3.1 Detailed Description	3
7.3.2 Constructor & Destructor Documentation	3
7.3.2.1 CustomException()	4
7.3.3 Member Function Documentation	4
7.3.3.1 description()	4
7.3.4 Member Data Documentation	4
7.3.4.1 what	4
7.4 qpp::exception::DimsInvalid Class Reference	5
7.4.1 Detailed Description	-6
7.4.2 Member Function Documentation	-6
7.4.2.1 description()	-6
7.4.2.2 Exception()	-6
7.5 qpp::exception::DimsMismatchCvector Class Reference	7
7.5.1 Detailed Description	8
7.5.2 Member Function Documentation	8
7.5.2.1 description()	8
7.5.2.2 Exception()	8
7.6 qpp::exception::DimsMismatchMatrix Class Reference	.9
7.6.1 Detailed Description	C
7.6.2 Member Function Documentation	Ю
7.6.2.1 description()	C
7.6.2.2 Exception()	C
7.7 qpp::exception::DimsMismatchRvector Class Reference	1
7.7.1 Detailed Description	2
7.7.2 Member Function Documentation	2
7.7.2.1 description()	2
7.7.2.2 Exception()	2
7.8 qpp::exception::DimsMismatchVector Class Reference	3
7.8.1 Detailed Description	i4
7.8.2 Member Function Documentation	14
7.8.2.1 description()	54

7.8.2.2 Exception()	54
7.9 qpp::exception::DimsNotEqual Class Reference	55
7.9.1 Detailed Description	56
7.9.2 Member Function Documentation	56
7.9.2.1 description()	56
7.9.2.2 Exception()	56
7.10 qpp::internal::Display_Impl_ Struct Reference	57
7.10.1 Member Function Documentation	57
7.10.1.1 display_impl_()	57
7.11 qpp::exception::Duplicates Class Reference	58
7.11.1 Detailed Description	59
7.11.2 Member Function Documentation	59
7.11.2.1 description()	59
7.11.2.2 Exception()	59
7.12 qpp::Dynamic_bitset Class Reference	59
7.12.1 Detailed Description	62
7.12.2 Member Typedef Documentation	62
7.12.2.1 storage_type	62
7.12.2.2 value_type	62
7.12.3 Constructor & Destructor Documentation	62
7.12.3.1 Dynamic_bitset()	62
7.12.3.2 ~Dynamic_bitset()	63
7.12.4 Member Function Documentation	63
7.12.4.1 all()	63
7.12.4.2 any()	63
7.12.4.3 count()	63
7.12.4.4 data()	64
7.12.4.5 display()	64
7.12.4.6 flip() [1/2]	64
7.12.4.7 flip() [2/2]	65
7.12.4.8 get()	65
7.12.4.9 index_()	65
7.12.4.10 none()	66
7.12.4.11 offset_()	66
7.12.4.12 operator"!=()	66
7.12.4.13 operator-()	67
7.12.4.14 operator==()	67
7.12.4.15 rand() [1/2]	67
7.12.4.16 rand() [2/2]	68
7.12.4.17 reset() [1/2]	68
7.12.4.18 reset() [2/2]	
7.12.4.19 set() [1/2]	69

7.12.4.20 set() [2/2]	39
7.12.4.21 size()	39
7.12.4.22 storage_size()	39
7.12.4.23 to_string()	70
7.12.5 Member Data Documentation	70
7.12.5.1 n	70
7.12.5.2 storage_size	70
7.12.5.3 v	71
7.13 qpp::internal::EqualEigen Class Reference	71
7.13.1 Detailed Description	71
7.13.2 Member Function Documentation	71
7.13.2.1 operator()()	71
7.14 qpp::internal::EqualSameSizeStringDits Class Reference	72
7.14.1 Detailed Description	72
7.14.2 Member Function Documentation	72
7.14.2.1 operator()()	72
7.15 qpp::exception::Exception Class Reference	73
7.15.1 Detailed Description	74
7.15.2 Constructor & Destructor Documentation	75
7.15.2.1 Exception()	75
7.15.3 Member Function Documentation	75
7.15.3.1 description()	75
7.15.3.2 what()	75
7.15.4 Member Data Documentation	<sup>7</sup> 6
7.15.4.1 msg	76
7.15.4.2 where	76
7.16 qpp::Gates Class Reference	<sup>7</sup> 6
7.16.1 Detailed Description	78
7.16.2 Constructor & Destructor Documentation	78
7.16.2.1 Gates()	78
7.16.2.2 ∼Gates()	79
7.16.3 Member Function Documentation	79
7.16.3.1 CTRL()	79
7.16.3.2 expandout() [1/3]	79
7.16.3.3 expandout() [2/3]	30
7.16.3.4 expandout() [3/3]	31
7.16.3.5 Fd()	31
7.16.3.6 get_name()	32
7.16.3.7 ld()	32
7.16.3.8 MODMUL()	33
7.16.3.9 Rn()	33
7.16.3.10 RX()	34

7.16.3.11 RY()	 . 184
7.16.3.12 RZ()	 . 184
7.16.3.13 SWAPd()	 . 185
7.16.3.14 Xd()	 . 185
7.16.3.15 Zd()	 . 185
7.16.4 Friends And Related Function Documentation	 . 186
7.16.4.1 internal::Singleton< const Gates >	 . 186
7.16.5 Member Data Documentation	 . 186
7.16.5.1 CNOT	 . 186
7.16.5.2 CNOTba	 . 186
7.16.5.3 CZ	 . 186
7.16.5.4 FRED	 . 187
7.16.5.5 H	 . 187
7.16.5.6 ld2	 . 187
7.16.5.7 S	 . 187
7.16.5.8 SWAP	 . 187
7.16.5.9 T	 . 187
7.16.5.10 TOF	 . 188
7.16.5.11 X	 . 188
7.16.5.12 Y	 . 188
7.16.5.13 Z	 . 188
7.17 qpp::QCircuit::GateStep Struct Reference	 . 189
7.17.1 Detailed Description	 . 190
7.17.2 Constructor & Destructor Documentation	 . 190
7.17.2.1 GateStep() [1/2]	 . 190
7.17.2.2 GateStep() [2/2]	 . 190
7.17.3 Member Data Documentation	 . 190
7.17.3.1 ctrl	 . 190
7.17.3.2 gate_hash	 . 191
7.17.3.3 gate_type	 . 191
7.17.3.4 name	 . 191
7.17.3.5 target	 . 191
7.18 qpp::internal::HashEigen Class Reference	 . 191
7.18.1 Detailed Description	 . 192
7.18.2 Member Function Documentation	 . 192
7.18.2.1 operator()()	 . 192
7.19 qpp::IDisplay Class Reference	 . 192
7.19.1 Detailed Description	 . 193
7.19.2 Constructor & Destructor Documentation	 . 193
7.19.2.1 ~IDisplay()	 . 193
7.19.3 Member Function Documentation	 . 193
7.19.3.1 display()	 . 193

7.19.4 Friends And Related Function Documentation	94
7.19.4.1 operator<<	94
7.20 qpp::IJSON Class Reference	94
7.20.1 Detailed Description	95
7.20.2 Constructor & Destructor Documentation	95
7.20.2.1 ~IJSON()	95
7.20.3 Member Function Documentation	95
7.20.3.1 to_JSON()	95
7.21 qpp::Init Class Reference	95
7.21.1 Detailed Description	96
7.21.2 Constructor & Destructor Documentation	97
7.21.2.1 Init()	97
7.21.2.2 ~Init()	97
7.21.3 Friends And Related Function Documentation	97
7.21.3.1 internal::Singleton < const Init >	97
7.22 qpp::exception::InvalidIterator Class Reference	97
7.22.1 Detailed Description	99
7.22.2 Member Function Documentation	99
7.22.2.1 description()	99
7.22.2.2 Exception()	99
7.23 qpp::internal::IOManipEigen Class Reference	99
7.23.1 Constructor & Destructor Documentation	01
7.23.1.1 IOManipEigen() [1/2]	01
7.23.1.2 IOManipEigen() [2/2]	01
7.23.2 Member Function Documentation	01
7.23.2.1 display()	01
7.23.3 Member Data Documentation	01
7.23.3.1 A	01
7.23.3.2 chop	02
7.24 qpp::internal::IOManipPointer< PointerType > Class Template Reference	02
7.24.1 Constructor & Destructor Documentation	03
7.24.1.1 IOManipPointer() [1/2]	03
7.24.1.2 IOManipPointer() [2/2]	03
7.24.2 Member Function Documentation	03
7.24.2.1 display()	04
7.24.2.2 operator=()	04
7.24.3 Member Data Documentation	04
7.24.3.1 chop	04
7.24.3.2 end	04
7.24.3.3 N	04
7.24.3.4 p	05
7.24.3.5 separator	05

7.24.3.6 start	. 205
$7.25~\text{qpp::internal::IOManipRange} < \text{InputIterator} > \text{Class Template Reference}~\dots~\dots~\dots~\dots~\dots~\dots~\dots~\dots~\dots~\dots~\dots~\dots~\dots~\dots~\dots~\dots~\dots~\dots~\dots$	. 205
7.25.1 Constructor & Destructor Documentation	. 206
7.25.1.1 IOManipRange() [1/2]	. 207
7.25.1.2 IOManipRange() [2/2]	. 207
7.25.2 Member Function Documentation	. 207
7.25.2.1 display()	. 207
7.25.2.2 operator=()	. 207
7.25.3 Member Data Documentation	. 207
7.25.3.1 chop	. 208
7.25.3.2 end	. 208
7.25.3.3 first	. 208
7.25.3.4 last	. 208
7.25.3.5 separator	. 208
7.25.3.6 start	. 208
7.26 qpp::is_complex $<$ T $>$ Struct Template Reference	. 209
7.26.1 Detailed Description	. 209
7.27 qpp::is_complex $<$ std::complex $<$ T $>$ $>$ Struct Template Reference	. 210
7.27.1 Detailed Description	. 210
7.28 qpp::is_iterable $<$ T, typename $>$ Struct Template Reference	. 211
7.28.1 Detailed Description	. 211
7.29 qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval< >().end()), decltype(*(std::declval< T >().begin()))>> Struct Template Reference	
	. 212
>().end()), decltype(*(std::declval< T >().begin()))> > Struct Template Reference	. 212 . 213
>().end()), decltype(*(std::declval< T >().begin()))> > Struct Template Reference	. 212 . 213 . 213
>().end()), decltype(*(std::declval < T >().begin()))> > Struct Template Reference	. 212 . 213 . 213 . 213
>().end()), decltype(*(std::declval < T >().begin()))> > Struct Template Reference 7.29.1 Detailed Description	<ul><li>. 212</li><li>. 213</li><li>. 213</li><li>. 214</li></ul>
>().end()), decltype(*(std::declval< T >().begin()))> > Struct Template Reference 7.29.1 Detailed Description  7.30 qpp::is_matrix_expression< Derived > Struct Template Reference 7.30.1 Detailed Description  7.31 qpp::QCircuit::iterator Class Reference	<ul><li>212</li><li>213</li><li>213</li><li>213</li><li>214</li><li>215</li></ul>
>().end()), decltype(*(std::declval < T >().begin()))> > Struct Template Reference 7.29.1 Detailed Description	. 212 . 213 . 213 . 213 . 214 . 215
>().end()), decltype(*(std::declval < T >().begin()))> > Struct Template Reference 7.29.1 Detailed Description  7.30 qpp::is_matrix_expression < Derived > Struct Template Reference 7.30.1 Detailed Description  7.31 qpp::QCircuit::iterator Class Reference 7.31.1 Detailed Description  7.31.2 Member Typedef Documentation	. 212 . 213 . 213 . 213 . 214 . 215 . 215
>().end()), decltype(*(std::declval < T >().begin()))> > Struct Template Reference 7.29.1 Detailed Description  7.30 qpp::is_matrix_expression < Derived > Struct Template Reference 7.30.1 Detailed Description  7.31 qpp::QCircuit::iterator Class Reference 7.31.1 Detailed Description  7.31.2 Member Typedef Documentation  7.31.2.1 difference_type	. 212 . 213 . 213 . 213 . 214 . 215 . 215 . 215
>().end()), decltype(*(std::declval < T >().begin()))> > Struct Template Reference 7.29.1 Detailed Description  7.30 qpp::is_matrix_expression < Derived > Struct Template Reference 7.30.1 Detailed Description  7.31 qpp::QCircuit::iterator Class Reference 7.31.1 Detailed Description  7.31.2 Member Typedef Documentation 7.31.2.1 difference_type 7.31.2.2 iterator_category	. 212 . 213 . 213 . 214 . 215 . 215 . 215 . 215
>().end()), decltype(*(std::declval < T >().begin()))> > Struct Template Reference 7.29.1 Detailed Description  7.30 qpp::is_matrix_expression < Derived > Struct Template Reference 7.30.1 Detailed Description  7.31 qpp::QCircuit::iterator Class Reference 7.31.1 Detailed Description  7.31.2 Member Typedef Documentation  7.31.2.1 difference_type  7.31.2.2 iterator_category  7.31.2.3 pointer	. 212 . 213 . 213 . 214 . 215 . 215 . 215 . 215 . 216
>().end()), decltype(*(std::declval< T >().begin()))> > Struct Template Reference 7.29.1 Detailed Description  7.30 qpp::is_matrix_expression< Derived > Struct Template Reference 7.30.1 Detailed Description  7.31 qpp::QCircuit::iterator Class Reference 7.31.1 Detailed Description 7.31.2 Member Typedef Documentation 7.31.2.1 difference_type 7.31.2.2 iterator_category 7.31.2.3 pointer 7.31.2.4 reference	. 212 . 213 . 213 . 214 . 215 . 215 . 215 . 216 . 216
>().end()), decltype(*(std::declval< T >().begin()))> > Struct Template Reference 7.29.1 Detailed Description  7.30 qpp::is_matrix_expression< Derived > Struct Template Reference 7.30.1 Detailed Description  7.31 qpp::QCircuit::iterator Class Reference 7.31.1 Detailed Description  7.31.2 Member Typedef Documentation 7.31.2.1 difference_type 7.31.2.2 iterator_category 7.31.2.3 pointer 7.31.2.4 reference 7.31.2.5 value_type	. 212 . 213 . 213 . 214 . 215 . 215 . 215 . 216 . 216 . 216
>().end()), decltype(*(std::declval < T >().begin()))> > Struct Template Reference 7.29.1 Detailed Description 7.30 qpp::is_matrix_expression < Derived > Struct Template Reference 7.30.1 Detailed Description 7.31 qpp::QCircuit::iterator Class Reference 7.31.1 Detailed Description 7.31.2 Member Typedef Documentation 7.31.2.1 difference_type 7.31.2.2 iterator_category 7.31.2.3 pointer 7.31.2.4 reference 7.31.2.5 value_type 7.31.3 Constructor & Destructor Documentation	. 212 . 213 . 213 . 214 . 215 . 215 . 215 . 216 . 216 . 216 . 216
>().end()), decltype(*(std::declval< T >().begin()))> > Struct Template Reference 7.29.1 Detailed Description 7.30 qpp::is_matrix_expression< Derived > Struct Template Reference 7.30.1 Detailed Description 7.31 qpp::QCircuit::iterator Class Reference 7.31.1 Detailed Description 7.31.2 Member Typedef Documentation 7.31.2.1 difference_type 7.31.2.2 iterator_category 7.31.2.3 pointer 7.31.2.4 reference 7.31.2.5 value_type 7.31.3 Constructor & Destructor Documentation 7.31.3.1 iterator() [1/2]	. 212 . 213 . 213 . 214 . 215 . 215 . 215 . 216 . 216 . 216 . 216 . 216
>().end()), decltype(*(std::declval< T >().begin()))>> Struct Template Reference 7.29.1 Detailed Description 7.30 qpp::is_matrix_expression< Derived > Struct Template Reference 7.30.1 Detailed Description 7.31 qpp::QCircuit::iterator Class Reference 7.31.1 Detailed Description 7.31.2 Member Typedef Documentation 7.31.2.1 difference_type 7.31.2.2 iterator_category 7.31.2.3 pointer 7.31.2.4 reference 7.31.2.5 value_type 7.31.3 Constructor & Destructor Documentation 7.31.3.1 iterator() [1/2] 7.31.3.2 iterator() [2/2]	. 212 . 213 . 213 . 214 . 215 . 215 . 215 . 216 . 216 . 216 . 216 . 216 . 216
>().end()), decltype(*(std::declval< T >().begin()))> > Struct Template Reference 7.29.1 Detailed Description 7.30 qpp::is_matrix_expression< Derived > Struct Template Reference 7.30.1 Detailed Description 7.31 qpp::QCircuit::iterator Class Reference 7.31.1 Detailed Description 7.31.2 Member Typedef Documentation 7.31.2.1 difference_type 7.31.2.2 iterator_category 7.31.2.3 pointer 7.31.2.4 reference 7.31.2.5 value_type 7.31.3 Constructor & Destructor Documentation 7.31.3.1 iterator() [1/2] 7.31.3.2 iterator() [2/2] 7.31.4 Member Function Documentation	. 212 . 213 . 213 . 214 . 215 . 215 . 215 . 216 . 216 . 216 . 216 . 216 . 216 . 216 . 216
>().end()), decltype(*(std::declval< T >().begin()))>> Struct Template Reference 7.29.1 Detailed Description 7.30 qpp::is_matrix_expression< Derived > Struct Template Reference 7.30.1 Detailed Description 7.31 qpp::QCircuit::iterator Class Reference 7.31.1 Detailed Description 7.31.2 Member Typedef Documentation 7.31.2.1 difference_type 7.31.2.2 iterator_category 7.31.2.3 pointer 7.31.2.4 reference 7.31.2.5 value_type 7.31.3 Constructor & Destructor Documentation 7.31.3.1 iterator() [1/2] 7.31.3.2 iterator() [2/2] 7.31.4 Member Function Documentation 7.31.4.1 operator *()	. 212 . 213 . 213 . 214 . 215 . 215 . 215 . 216 . 216 . 216 . 216 . 216 . 216 . 216 . 217 . 217

7.31.4.5 operator=()	18
7.31.4.6 operator==()	18
7.31.4.7 set_begin_()	18
7.31.4.8 set_end_()	18
7.31.5 Member Data Documentation	19
7.31.5.1 elem	19
7.31.5.2 qc	19
7.32 qpp::make_void < Ts > Struct Template Reference	19
7.32.1 Detailed Description	19
7.32.2 Member Typedef Documentation	20
7.32.2.1 type	20
7.33 qpp::exception::MatrixMismatchSubsys Class Reference	20
7.33.1 Detailed Description	21
7.33.2 Member Function Documentation	21
7.33.2.1 description()	22
7.33.2.2 Exception()	22
7.34 qpp::exception::MatrixNotCvector Class Reference	22
7.34.1 Detailed Description	24
7.34.2 Member Function Documentation	24
7.34.2.1 description()	24
7.34.2.2 Exception()	24
7.35 qpp::exception::MatrixNotRvector Class Reference	24
7.35.1 Detailed Description	26
7.35.2 Member Function Documentation	26
7.35.2.1 description()	26
7.35.2.2 Exception()	26
7.36 qpp::exception::MatrixNotSquare Class Reference	26
7.36.1 Detailed Description	28
7.36.2 Member Function Documentation	28
7.36.2.1 description()	28
7.36.2.2 Exception()	28
7.37 qpp::exception::MatrixNotSquareNorCvector Class Reference	28
7.37.1 Detailed Description	30
7.37.2 Member Function Documentation	30
7.37.2.1 description()	30
7.37.2.2 Exception()	30
7.38 qpp::exception::MatrixNotSquareNorRvector Class Reference	30
7.38.1 Detailed Description	32
7.38.2 Member Function Documentation	32
7.38.2.1 description()	32
7.38.2.2 Exception()	32
7.39 gpp::exception::MatrixNotSquareNorVector Class Reference	32

7.39.1 Detailed Description	34
7.39.2 Member Function Documentation	34
7.39.2.1 description()	34
7.39.2.2 Exception()	34
7.40 qpp::exception::MatrixNotVector Class Reference	34
7.40.1 Detailed Description	36
7.40.2 Member Function Documentation	36
7.40.2.1 description()	36
7.40.2.2 Exception()	36
7.41 qpp::QCircuit::MeasureStep Struct Reference	36
7.41.1 Detailed Description	37
7.41.2 Constructor & Destructor Documentation	37
7.41.2.1 MeasureStep() [1/2]	38
7.41.2.2 MeasureStep() [2/2]	38
7.41.3 Member Data Documentation	38
7.41.3.1 c_reg	38
7.41.3.2 mats_hash	38
7.41.3.3 measurement_type	38
7.41.3.4 name	39
7.41.3.5 target	39
7.42 qpp::exception::NoCodeword Class Reference	39
7.42.1 Detailed Description	40
7.42.2 Member Function Documentation	40
7.42.2.1 description()	40
7.42.2.2 Exception()	41
7.43 qpp::NoiseBase< T > Class Template Reference	41
7.43.1 Detailed Description	43
7.43.2 Member Typedef Documentation	43
7.43.2.1 noise_type	43
7.43.3 Constructor & Destructor Documentation	43
7.43.3.1 NoiseBase() [1/2]	43
7.43.3.2 NoiseBase() [2/2]	43
7.43.3.3 ∼NoiseBase()	44
7.43.4 Member Function Documentation	44
7.43.4.1 compute_probs_()	44
7.43.4.2 compute_state_()	45
7.43.4.3 get_d()	45
7.43.4.4 get_Ks()	45
7.43.4.5 get_last_idx()	46
7.43.4.6 get_last_K()	46
7.43.4.7 get_last_p()	46
7.43.4.8 get_probs()	46

7.43.4.9 operator()() [1/3]
7.43.4.10 operator()() [2/3]
7.43.4.11 operator()() [3/3]
7.43.5 Member Data Documentation
7.43.5.1 d
7.43.5.2 generated
7.43.5.3 i
7.43.5.4 Ks
7.43.5.5 probs
7.44 qpp::NoiseType Class Reference
7.44.1 Detailed Description
7.45 qpp::exception::NotBipartite Class Reference
7.45.1 Detailed Description
7.45.2 Member Function Documentation
7.45.2.1 description()
7.45.2.2 Exception()
7.46 qpp::exception::NotImplemented Class Reference
7.46.1 Detailed Description
7.46.2 Member Function Documentation
7.46.2.1 description()
7.46.2.2 Exception()
7.47 qpp::exception::NotQubitCvector Class Reference
7.47.1 Detailed Description
7.47.2 Member Function Documentation
7.47.2.1 description()
7.47.2.2 Exception()
7.48 qpp::exception::NotQubitMatrix Class Reference
7.48.1 Detailed Description
7.48.2 Member Function Documentation
7.48.2.1 description()
7.48.2.2 Exception()
7.49 qpp::exception::NotQubitRvector Class Reference
7.49.1 Detailed Description
7.49.2 Member Function Documentation
7.49.2.1 description()
7.49.2.2 Exception()
7.50 qpp::exception::NotQubitSubsys Class Reference
7.50.1 Detailed Description
7.50.2 Member Function Documentation
7.50.2.1 description()
7.50.2.2 Exception()
7.51 app::exception::NotQubitVector Class Reference

7.51.1 Detailed Description	3
7.51.2 Member Function Documentation	3
7.51.2.1 description()	3
7.51.2.2 Exception()	3
7.52 qpp::exception::OutOfRange Class Reference	3
7.52.1 Detailed Description	55
7.52.2 Member Function Documentation	5
7.52.2.1 description()	55
7.52.2.2 Exception()	5
7.53 qpp::exception::PermInvalid Class Reference	5
7.53.1 Detailed Description	57
7.53.2 Member Function Documentation	7ز
7.53.2.1 description()	7ز
7.53.2.2 Exception()	7ز
7.54 qpp::exception::PermMismatchDims Class Reference	7ز
7.54.1 Detailed Description	9
7.54.2 Member Function Documentation	9
7.54.2.1 description()	9
7.54.2.2 Exception()	9
7.55 qpp::QCircuit Class Reference	'0
7.55.1 Detailed Description	'4
7.55.2 Member Typedef Documentation	'4
7.55.2.1 const_iterator	'5
7.55.3 Member Enumeration Documentation	'5
7.55.3.1 GateType	'5
7.55.3.2 MeasureType	'5
7.55.3.3 StepType	7
7.55.4 Constructor & Destructor Documentation	7
7.55.4.1 QCircuit()	7
7.55.4.2 ~QCircuit()	'8
7.55.5 Member Function Documentation	'8
7.55.5.1 add_circuit()	'8
7.55.5.2 add_dit()	'8
7.55.5.3 add_hash_()	'9
7.55.5.4 add_qudit()	'9
7.55.5.5 begin() [1/2]	30
7.55.5.6 begin() [2/2]	30
7.55.5.7 cbegin()	0
7.55.5.8 cCTRL() [1/4]	0
7.55.5.9 cCTRL() [2/4]	31
7.55.5.10 cCTRL() [3/4]	31
7.55.5.11 cCTRL() [4/4]	32

7.55.5.12 cCTRL_custom()
7.55.5.13 cend()
7.55.5.14 CTRL() [1/4]
7.55.5.15 CTRL() [2/4]
7.55.5.16 CTRL() [3/4]
7.55.5.17 CTRL() [4/4]
7.55.5.18 CTRL_custom()
7.55.5.19 display()
7.55.5.20 end() [1/2]
7.55.5.21 end() [2/2]
7.55.5.22 gate() [1/3]
7.55.5.23 gate() [2/3]
7.55.5.24 gate() [3/3]
7.55.5.25 gate_custom()
7.55.5.26 gate_fan() [1/3]
7.55.5.27 gate_fan() [2/3]
7.55.5.28 gate_fan() [3/3]
7.55.5.29 get_cmat_hash_tbl_()
7.55.5.30 get_d()
7.55.5.31 get_depth()
7.55.5.32 get_gate_count()
7.55.5.33 get_gates_()
7.55.5.34 get_measured() [1/2]
7.55.5.35 get_measured() [2/2]
7.55.5.36 get_measurement_count() [1/2]
7.55.5.37 get_measurement_count() [2/2]
7.55.5.38 get_measurements_()
7.55.5.39 get_name()
7.55.5.40 get_nc()
7.55.5.41 get_non_measured()
7.55.5.42 get_nop_count()
7.55.5.43 get_nq()
7.55.5.44 get_step_count()
7.55.5.45 kron()
7.55.5.46 measureV() [1/2]
7.55.5.47 measureV() [2/2]
7.55.5.48 measureZ() [1/2]
7.55.5.49 measureZ() [2/2]
7.55.5.50 nop()
7.55.5.51 QFT() [1/3]
7.55.5.52 QFT() [2/3]
7.55.5.53 QFT() [3/3]

7.55.5.4 replicate()	298
<b>7.55.5.55 TFQ()</b> [1/3]	298
<b>7.55.5.56 TFQ()</b> [2/3]	300
<b>7.55.5.57 TFQ()</b> [3/3]	300
7.55.5.58 to_JSON()	301
7.55.6 Friends And Related Function Documentation	301
7.55.6.1 operator<< [1/4]	301
7.55.6.2 operator<< [2/4]	301
7.55.6.3 operator<< [3/4]	302
7.55.6.4 operator<< [4/4]	302
7.55.6.5 QEngine	303
7.55.7 Member Data Documentation	303
7.55.7.1 cmat_hash_tbl	303
7.55.7.2 count	303
7.55.7.3 d	303
7.55.7.4 gates	303
7.55.7.5 measured	303
7.55.7.6 measurement_count	304
7.55.7.7 measurements	304
7.55.7.8 name	304
7.55.7.9 nc	304
7.55.7.10 nq	304
7.55.7.11 step_types	304
7.56 qpp::QEngine Class Reference	305
7.56.1 Detailed Description	307
7.56.2 Constructor & Destructor Documentation	307
7.56.2.1 QEngine() [1/3]	307
<b>7.56.2.2 QEngine()</b> [2/3]	308
<b>7.56.2.3 QEngine()</b> [3/3]	308
7.56.2.4 ~QEngine()	308
7.56.3 Member Function Documentation	308
7.56.3.1 display()	308
7.56.3.2 execute() [1/3]	309
7.56.3.3 execute() [2/3]	309
<b>7.56.3.4 execute()</b> [3/3]	309
7.56.3.5 get_circuit()	310
7.56.3.6 get_dit()	310
7.56.3.7 get_dits()	310
7.56.3.8 get_measured() [1/2]	310
7.56.3.9 get_measured() [2/2]	311
7.56.3.10 get_non_measured()	311
7.56.3.11 get_probs()	311

7.56.3.12 get_psi()	. 312
7.56.3.13 get_relative_pos_()	. 312
7.56.3.14 get_stats()	. 312
7.56.3.15 operator=()	. 312
7.56.3.16 reset()	. 313
7.56.3.17 reset_stats()	. 313
7.56.3.18 set_dit()	. 313
7.56.3.19 set_measured_()	. 313
7.56.3.20 set_psi()	. 314
7.56.3.21 to_JSON()	. 314
7.56.4 Member Data Documentation	. 314
7.56.4.1 dits	. 315
7.56.4.2 probs	. 315
7.56.4.3 psi	. 315
7.56.4.4 qc	. 315
7.56.4.5 stats	. 315
7.56.4.6 subsys	. 315
7.57 qpp::QNoisyEngine < NoiseModel > Class Template Reference	. 316
7.57.1 Detailed Description	. 317
7.57.2 Constructor & Destructor Documentation	. 317
7.57.2.1 QNoisyEngine()	. 317
7.57.3 Member Function Documentation	. 318
7.57.3.1 execute() [1/4]	. 318
7.57.3.2 execute() [2/4]	. 318
7.57.3.3 execute() [3/4]	. 318
7.57.3.4 execute() [4/4]	. 319
7.57.3.5 get_noise_results()	. 319
7.57.4 Member Data Documentation	. 319
7.57.4.1 noise	. 319
7.57.4.2 noise_results	. 320
7.58 qpp::QubitAmplitudeDampingNoise Class Reference	. 320
7.58.1 Detailed Description	. 321
7.58.2 Constructor & Destructor Documentation	. 321
7.58.2.1 QubitAmplitudeDampingNoise()	. 321
7.59 qpp::QubitBitFlipNoise Class Reference	. 321
7.59.1 Detailed Description	. 322
7.59.2 Constructor & Destructor Documentation	. 323
7.59.2.1 QubitBitFlipNoise()	. 323
7.60 qpp::QubitBitPhaseFlipNoise Class Reference	. 323
7.60.1 Detailed Description	. 324
7.60.2 Constructor & Destructor Documentation	. 324
7.60.2.1 QubitBitPhaseFlipNoise()	. 324

7.61 qpp::QubitDepolarizingNoise Class Reference
7.61.1 Detailed Description
7.61.2 Constructor & Destructor Documentation
7.61.2.1 QubitDepolarizingNoise()
7.62 qpp::QubitPhaseDampingNoise Class Reference
7.62.1 Detailed Description
7.62.2 Constructor & Destructor Documentation
7.62.2.1 QubitPhaseDampingNoise()
7.63 qpp::QubitPhaseFlipNoise Class Reference
7.63.1 Detailed Description
7.63.2 Constructor & Destructor Documentation
7.63.2.1 QubitPhaseFlipNoise()
7.64 qpp::exception::QuditAlreadyMeasured Class Reference
7.64.1 Detailed Description
7.64.2 Member Function Documentation
7.64.2.1 description()
7.64.2.2 Exception()
7.65 qpp::QuditDepolarizingNoise Class Reference
7.65.1 Detailed Description
7.65.2 Constructor & Destructor Documentation
7.65.2.1 QuditDepolarizingNoise()
7.65.3 Member Function Documentation
7.65.3.1 fill_Ks_()
7.65.3.2 fill_probs_()
7.66 qpp::RandomDevices Class Reference
7.66.1 Detailed Description
7.66.2 Constructor & Destructor Documentation
7.66.2.1 RandomDevices()
7.66.2.2 ~RandomDevices()
7.66.3 Member Function Documentation
7.66.3.1 get_prng()
7.66.3.2 load()
7.66.3.3 save()
7.66.4 Friends And Related Function Documentation
7.66.4.1 internal::Singleton < RandomDevices >
7.66.5 Member Data Documentation
7.66.5.1 prng
7.66.5.2 rd
7.67 qpp::internal::Singleton < T > Class Template Reference
7.67.1 Detailed Description
7.67.2 Constructor & Destructor Documentation
7.67.2.1 Singleton() [1/2]

7.67.2.2 Singleton() [2/2] 3	39
7.67.2.3 ~Singleton()	39
7.67.3 Member Function Documentation	39
7.67.3.1 get_instance()	39
7.67.3.2 get_thread_local_instance()	39
7.67.3.3 operator=()	39
7.68 qpp::exception::SizeMismatch Class Reference	40
7.68.1 Detailed Description	41
7.68.2 Member Function Documentation	41
7.68.2.1 description()	41
7.68.2.2 Exception()	41
7.69 qpp::NoiseType::StateDependent Class Reference	42
7.69.1 Detailed Description	42
7.70 qpp::NoiseType::StateIndependent Class Reference	42
7.70.1 Detailed Description	42
7.71 qpp::States Class Reference	42
7.71.1 Detailed Description	44
7.71.2 Constructor & Destructor Documentation	45
7.71.2.1 States()	45
7.71.2.2 ~States()	45
7.71.3 Member Function Documentation	45
7.71.3.1 jn()	45
7.71.3.2 mes()	45
7.71.3.3 minus()	46
7.71.3.4 one()	46
7.71.3.5 plus()	47
7.71.3.6 zero()	47
7.71.4 Friends And Related Function Documentation	47
7.71.4.1 internal::Singleton < const States >	47
7.71.5 Member Data Documentation	47
7.71.5.1 b00	48
7.71.5.2 b01	48
7.71.5.3 b10	48
7.71.5.4 b11	48
7.71.5.5 GHZ	48
7.71.5.6 pb000	48
7.71.5.7 pb01	49
7.71.5.8 pb10	49
7.71.5.9 pb11	49
7.71.5.10 pGHZ	49
7.71.5.11 pW	49
7.71.5.12 px0	49

7.71.5.13 px1
7.71.5.14 py0
7.71.5.15 py1
7.71.5.16 pz0
7.71.5.17 pz1
7.71.5.18 W
7.71.5.19 x0
7.71.5.20 x1
7.71.5.21 y0
7.71.5.22 y1
7.71.5.23 z0
7.71.5.24 z1
7.72 qpp::exception::SubsysMismatchDims Class Reference
7.72.1 Detailed Description
7.72.2 Member Function Documentation
7.72.2.1 description()
7.72.2.2 Exception()
7.73 qpp::Timer < T, CLOCK_T > Class Template Reference
7.73.1 Detailed Description
7.73.2 Constructor & Destructor Documentation
7.73.2.1 Timer()
7.73.2.2 ~Timer()
7.73.3 Member Function Documentation
7.73.3.1 display()
7.73.3.2 get_duration()
7.73.3.3 tic()
7.73.3.4 tics()
7.73.3.5 toc()
7.73.4 Member Data Documentation
7.73.4.1 end
7.73.4.2 start
7.74 qpp::exception::TypeMismatch Class Reference
7.74.1 Detailed Description
7.74.2 Member Function Documentation
7.74.2.1 description()
7.74.2.2 Exception()
7.75 qpp::exception::UndefinedType Class Reference
7.75.1 Detailed Description
7.75.2 Member Function Documentation
7.75.2.1 description()
7.75.2.2 Exception()
7.76 gpp://exception:/Llnknown.Class.Reference

	7.76.1 Detailed Description	363
	7.76.2 Member Function Documentation	363
	7.76.2.1 description()	363
	7.76.2.2 Exception()	364
	7.77 qpp::QCircuit::iterator::value_type_ Class Reference	364
	7.77.1 Detailed Description	365
	7.77.2 Constructor & Destructor Documentation	365
	7.77.2.1 value_type_() [1/2]	365
	7.77.2.2 value_type_() [2/2]	366
	7.77.3 Member Function Documentation	366
	7.77.3.1 display()	366
	7.77.3.2 operator=()	366
	7.77.4 Member Data Documentation	366
	7.77.4.1 gates_ip	367
	7.77.4.2 ip	367
	7.77.4.3 measurements_ip	367
	7.77.4.4 type	367
	7.77.4.5 value_type_qc	367
	7.78 qpp::exception::ZeroSize Class Reference	368
	7.78.1 Detailed Description	369
	7.78.2 Member Function Documentation	369
	7.78.2.1 description()	369
	7.78.2.2 Exception()	369
8	File Documentation	371
	8.1 classes/circuits/circuits.h File Reference	
	8.1.1 Detailed Description	
	8.2 classes/circuits/engines.h File Reference	
	8.2.1 Detailed Description	
		373
	and the same of th	373
	•	373
	•	375
		375
	•	376
	8.6 classes/idisplay.h File Reference	376
	8.6.1 Detailed Description	377
	8.7 classes/init.h File Reference	377
	The state of the s	377
	8.8 classes/noise.h File Reference	378
	8.8.1 Detailed Description	378
	8.9 classes/random devices.h File Reference	379

8.9.1 Detailed Description	79
8.10 classes/reversible.h File Reference	79
8.10.1 Detailed Description	80
8.11 classes/states.h File Reference	80
8.11.1 Detailed Description	81
8.12 classes/timer.h File Reference	81
8.12.1 Detailed Description	81
8.13 constants.h File Reference	82
8.13.1 Detailed Description	83
8.14 entanglement.h File Reference	83
8.14.1 Detailed Description	85
8.15 entropies.h File Reference	85
8.15.1 Detailed Description	86
8.16 experimental/experimental.h File Reference	86
8.16.1 Detailed Description	86
8.17 functions.h File Reference	86
8.17.1 Detailed Description	91
8.18 input_output.h File Reference	91
8.18.1 Detailed Description	92
8.19 instruments.h File Reference	92
8.19.1 Detailed Description	94
8.20 internal/classes/iomanip.h File Reference	94
8.20.1 Detailed Description	94
8.21 internal/classes/singleton.h File Reference	95
8.21.1 Detailed Description	95
8.22 internal/util.h File Reference	95
8.22.1 Detailed Description	97
8.23 MATLAB/matlab.h File Reference	97
8.23.1 Detailed Description	98
8.24 number_theory.h File Reference	98
8.24.1 Detailed Description	99
8.25 operations.h File Reference	00
8.25.1 Detailed Description	02
8.26 qpp.h File Reference	02
8.26.1 Detailed Description	03
8.26.2 Macro Definition Documentation	03
8.26.2.1 QPP_UNUSED	03
8.27 random.h File Reference	04
8.27.1 Detailed Description	05
8.28 statistics.h File Reference	05
8.28.1 Detailed Description	06
8.29 traits.h File Reference	06

Δ	11.
4	.09
4	.09
4	-08
4	07

## **Chapter 1**

### Quantum++

Version 1.3 - 25 July 2019

Build status:

Chat (questions/issues)

#### **About**

Quantum++ is a modern C++11 general purpose quantum computing library, composed solely of template header files. Quantum++ is written in standard C++11 and has very low external dependencies, using only the Eigen 3 linear algebra header-only template library and, if available, the OpenMP multi-processing library.

Quantum++ is not restricted to qubit systems or specific quantum information processing tasks, being capable of simulating arbitrary quantum processes. The main design factors taken in consideration were the ease of use, high portability, and high performance. The library's simulation capabilities are only restricted by the amount of available physical memory. On a typical machine (Intel i5 8Gb RAM) Quantum++ can successfully simulate the evolution of 25 qubits in a pure state or of 12 qubits in a mixed state reasonably fast.

To report any bugs or ask for additional features/enhancements, please submit an issue with an appropriate label.

If you are interesting in contributing to this project, feel free to contact me. Alternatively, create a custom branch, add your contribution, then finally create a pull request. If I accept the pull request, I will merge your custom branch with the latest development branch. The latter will eventually be merged into a future release version. To contribute, you need to have a solid knowledge of C++ (preferably C++11), including templates and the standard library, a basic knowledge of quantum computing and linear algebra, and working experience with Eigen 3.

For additional Eigen 3 documentation see <a href="http://eigen.tuxfamily.org/dox/">http://eigen.tuxfamily.org/dox/</a>. For a simple Eigen 3 quick ASCII reference see <a href="http://eigen.tuxfamily.org/dox/AsciiQuick←">http://eigen.tuxfamily.org/dox/AsciiQuick←</a> Reference.txt.

Copyright (c) 2013 - 2019 Vlad Gheorghiu, vgheorgh AT gmail DOT com.

2 Quantum++

### License

Quantum++ is distributed under the MIT license. Please see the LICENSE file for more details.

### Installation instructions and further documentation

Please see the installation guide `INSTALL.md` and the comprehensive Wiki for further documentation and detailed examples.

The official API documentation is available in PDF and HTML formats in the doc folder.

## **Chapter 2**

# Namespace Index

## 2.1 Namespace List

Here is a list of all namespaces with brief descriptions:

qpp	
Quantum++ main namespace	Ę
qpp::exception	
Quantum++ exception hierarchy namespace	8
qpp::experimental	
Experimental/test functions/classes, do not use or modify	2(
qpp::internal	
Internal utility functions, do not use them directly or modify them	20
qpp::literals	35

4 Namespace Index

# **Chapter 3**

# **Hierarchical Index**

## 3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

qpp::internal::Display_Impl
qpp::internal::IOManipEigen
qpp::internal::EqualEigen
qpp::internal::EqualSameSizeStringDits
std::exception
qpp::exception::Exception
qpp::exception::CustomException
qpp::exception::DimsInvalid
qpp::exception::DimsMismatchCvector
qpp::exception::DimsMismatchMatrix
qpp::exception::DimsMismatchRvector
qpp::exception::DimsMismatchVector
app::exception::DimsNotEqual
qpp::exception::Duplicates
app::exception::InvalidIterator
qpp::exception::MatrixMismatchSubsys
qpp::exception::MatrixNotCvector
qpp::exception::MatrixNotRvector
qpp::exception::MatrixNotSquare
qpp::exception::MatrixNotSquareNorCvector
qpp::exception::MatrixNotSquareNorRvector
qpp::exception::MatrixNotSquareNorVector
qpp::exception::MatrixNotVector
qpp::exception::NoCodeword
qpp::exception::NotBipartite
qpp::exception::NotImplemented
qpp::exception::NotQubitCvector
qpp::exception::NotQubitMatrix
qpp::exception::NotQubitRvector
qpp::exception::NotQubitSubsys
qpp::exception::NotQubitVector
qpp::exception::OutOfRange
qpp::exception::PermInvalid
qpp::exception::PermMismatchDims
qpp::exception::QuditAlreadyMeasured

6 Hierarchical Index

qpp::exception::SizeMismatch	340
qpp::exception::SubsysMismatchDims	352
qpp::exception::TypeMismatch	
qpp::exception::UndefinedType	
qpp::exception::Unknown	
qpp::exception::ZeroSize	368
false_type	
qpp::is_complex < T >	
qpp::is_iterable < T, typename >	
qpp::QCircuit::GateStep	
qpp::internal::HashEigen     qpp::IDisplay	
qpp::Dynamic_bitset	
qpp::Bit_circuit	
qpp::internal::IOManipEigen	
qpp::internal::IOManipPointer< PointerType >	
qpp::internal::IOManipRange< InputIterator >	
<pre>qpp::QCircuit</pre>	
qpp::QEngine	
qpp::QNoisyEngine < NoiseModel >	
",	
qpp::Timer< T, CLOCK_T >	
qpp::IJSON	
qpp::QCircuit	
qpp::QEngine	305
is_base_of	
qpp::is_matrix_expression< Derived >	
qpp::QCircuit::iterator	
qpp::make_void < Ts >	
qpp::QCircuit::MeasureStep	
<pre>qpp::NoiseBase &lt; T &gt;</pre>	
qpp::QubitAmplitudeDampingNoise	
qpp::QubitPhaseDampingNoise	
${\tt qpp::NoiseBase} < {\tt NoiseType::StateIndependent} > . \ . \ . \ . \ . \ . \ . \ . \ . \ .$	
qpp::QubitBitFlipNoise	
qpp::QubitBitPhaseFlipNoise	
qpp::QubitDepolarizingNoise	
qpp::QubitPhaseFlipNoise	
qpp::QuditDepolarizingNoise	
qpp::NoiseType	
qpp::internal::Singleton < T >	
qpp::internal::Singleton < const Codes >	
qpp::Codes	
qpp::internal::Singleton< const Gates >	
qpp::Gates	176
$qpp :: Internal :: Singleton < const \; Init > \dots $	337
qpp::Init	195
qpp::internal::Singleton< const States >	337
qpp::States	
qpp::internal::Singleton< RandomDevices >	
qpp::RandomDevices	
qpp::NoiseType::StateDependent	
qpp::NoiseType::StateIndependent	342
true_type	

3.1 Class Hierarchy 7

qpp::is_complex< std::complex< T >>	. 210
$qpp::is\_iterable < T$ , $to\_void < decltype(std::declval < T > ().begin())$ , $decltype(std::declval < T > ().begin())$	•
>().end()), decltype(*(std::declval< T $>$ ().begin()))>>	. 212

8 Hierarchical Index

# **Chapter 4**

# **Class Index**

# 4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

qpp::Bit_circuit
Classical reversible circuit simulator
qpp::Codes
Const Singleton class that defines quantum error correcting codes
qpp::exception::CustomException
Custom exception
qpp::exception::DimsInvalid
Invalid dimension(s) exception
qpp::exception::DimsMismatchCvector
Dimension(s) mismatch column vector size exception
qpp::exception::DimsMismatchMatrix
Dimension(s) mismatch matrix size exception
qpp::exception::DimsMismatchRvector
Dimension(s) mismatch row vector size exception
qpp::exception::DimsMismatchVector
Dimension(s) mismatch vector size exception
qpp::exception::DimsNotEqual
Dimensions not equal exception
qpp::internal::Display_Impl
qpp::exception::Duplicates
System (e.g. std::vector) has duplicates exception
qpp::Dynamic_bitset
Dynamic bitset class, allows the specification of the number of bits at runtime
qpp::internal::EqualEigen
Functor for comparing Eigen expressions for equality
qpp::internal::EqualSameSizeStringDits
Functor for comparing strings of numbers of equal sizes in lexicographical order. Establishes a
strict weak ordering relation
qpp::exception::Exception
Base class for generating Quantum++ custom exceptions
qpp::Gates
Const Singleton class that implements most commonly used gates
qpp::QCircuit::GateStep
One step consisting only of gates/operators in the circuit
qpp::internal::HashEigen
Functor for hashing Eigen expressions

10 Class Index

qpp::IDisplay	
Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream 192	& os) const
qpp::IJSON	
Abstract class (interface) that mandates the definition of very basic JSON serialization support	194
qpp::Init	
Const Singleton class that performs additional initializations/cleanups	195
qpp::exception::InvalidIterator	
Invalid iterator	197
qpp::internal::IOManipEigen	199
qpp::internal::IOManipPointer< PointerType >	202
qpp::internal::IOManipRange< InputIterator >	205
qpp::is_complex< T >	
Checks whether the type is a complex type	209
qpp::is_complex< std::complex< T >>	
Checks whether the type is a complex number type, specialization for complex types	210
qpp::is_iterable < T, typename >	
Checks whether $T$ is compatible with an STL-like iterable container	211
$qpp::is\_iterable < T, \ to\_void < \ decltype(std::declval < T > ().begin()), \ decltype(std::declval < T > ().end()), \ decltype(std::declval < T > ().end()),$	ecltype(*(std::declval<
Checks whether $T$ is compatible with an STL-like iterable container, specialization for STL-like	
iterable containers	212
qpp::is_matrix_expression< Derived >	
Checks whether the type is an Eigen matrix expression	213
qpp::QCircuit::iterator	
Quantum circuit bound-checking (safe) iterator	214
qpp::make_void < Ts >	
Helper for qpp::to_void<> alias template	219
qpp::exception::MatrixMismatchSubsys	
Matrix mismatch subsystems exception	220
qpp::exception::MatrixNotCvector	
Matrix is not a column vector exception	222
qpp::exception::MatrixNotRvector	
Matrix is not a row vector exception	224
qpp::exception::MatrixNotSquare	
Matrix is not square exception	226
qpp::exception::MatrixNotSquareNorCvector	
Matrix is not square nor column vector exception	228
qpp::exception::MatrixNotSquareNorRvector	
Matrix is not square nor row vector exception	230
qpp::exception::MatrixNotSquareNorVector	
Matrix is not square nor vector exception	232
qpp::exception::MatrixNotVector	
Matrix is not a vector exception	234
qpp::QCircuit::MeasureStep	
One step consisting only of measurements in the circuit	236
qpp::exception::NoCodeword	
Codeword does not exist exception	239
qpp::NoiseBase< T >	
Base class for all noise models, derive your particular noise model	241
qpp::NoiseType	
Contains template tags used to specify the noise type	249
qpp::exception::NotBipartite	
Not bi-partite exception	249
qpp::exception::NotImplemented	
Code not yet implemented	251
qpp::exception::NotQubitCvector	
Column vector is not 2 x 1 exception	253

4.1 Class List

qpp::exception::NotQubitMatrix	
Matrix is not 2 x 2 exception	255
qpp::exception::NotQubitRvector	
Row vector is not 1 x 2 exception	257
qpp::exception::NotQubitSubsys	
Subsystems are not qubits exception	259
qpp::exception::NotQubitVector	
Vector is not 2 x 1 nor 1 x 2 exception	261
qpp::exception::OutOfRange	20
Argument out of range exception	263
qp::exception::PermInvalid	200
	265
Invalid permutation exception	200
qpp::exception::PermMismatchDims	00-
Permutation mismatch dimensions exception	267
qpp::QCircuit	070
Quantum circuit description	270
qpp::QEngine	
Quantum circuit engine, executes qpp::QCircuit	305
qpp::QNoisyEngine < NoiseModel >	
Noisy quantum circuit engine, executes qpp::QCircuit	316
qpp::QubitAmplitudeDampingNoise	
Qubit amplitude damping noise, as described in Nielsen and Chuang	320
qpp::QubitBitFlipNoise	
Qubit bit flip noise	321
qpp::QubitBitPhaseFlipNoise	
Qubit bit-phase flip (dephasing) noise	323
qpp::QubitDepolarizingNoise	
Qubit depolarizing noise	325
qpp::QubitPhaseDampingNoise	
Qubit phase damping noise, as described in Nielsen and Chuang	326
qpp::QubitPhaseFlipNoise	
Qubit phase flip (dephasing) noise	328
qpp::exception::QuditAlreadyMeasured	
Qudit was already measured exception	329
qpp::QuditDepolarizingNoise	0_0
Qudit depolarizing noise	331
qpp::RandomDevices	30
Singleton class that manages the source of randomness in the library	33/
app::internal::Singleton < T >	33-
Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously	
recurring template pattern)	337
	331
qp::exception::SizeMismatch	240
Size mismatch exception	340
qpp::NoiseType::StateDependent	0.46
Template tag, used whenever the noise is state-dependent	342
qpp::NoiseType::StateIndependent	
Template tag, used whenever the noise is state-independent	342
qpp::States	
Const Singleton class that implements most commonly used states	342
qpp::exception::SubsysMismatchDims	
Subsystems mismatch dimensions exception	352
qpp::Timer< T, CLOCK_T >	
Chronometer	354
qpp::exception::TypeMismatch	
Type mismatch exception	358
qpp::exception::UndefinedType	
Not defined for this type exception	360

12 Class Index

qpp::exception::Unknown	
Unknown exception	362
qpp::QCircuit::iterator::value_type_	
Value type class for qpp::QCircuit::iterator	364
qpp::exception::ZeroSize	
Object has zero size exception	368

# **Chapter 5**

# File Index

# 5.1 File List

Here is a list of all files with brief descriptions:

constants.h	
Constants	82
entanglement.h	
Entanglement functions	83
entropies.h	
Entropy functions	35
functions.h	
Generic quantum computing functions	36
input_output.h	
Input/output functions	91
instruments.h	
Measurement functions	92
number_theory.h	
Number theory functions	98
operations.h	
Quantum operation functions	C
qpp.h	
Quantum++ main header file, includes all other necessary headers	)2
random.h	
Randomness-related functions	ე4
statistics.h	
Statistics functions	)5
traits.h	
Type traits	Э6
types.h	
Type aliases	JE
classes/codes.h	
Quantum error correcting codes	73
classes/exception.h	
Exceptions	73
classes/gates.h	
Quantum gates	75
classes/idisplay.h	
Display interface via the non-virtual interface (NVI) and very basic JSON serialization support	
interface	76

14 File Index

classes/init.h	
Initialization	. 377
classes/noise.h	
Noise models	. 378
classes/random_devices.h	
Random devices	. 379
classes/reversible.h	
Support for classical reversible circuits	. 379
classes/states.h	
Quantum states	. 380
classes/timer.h	
Timing	. 381
classes/circuits/circuits.h	
Qudit quantum circuits	. 371
classes/circuits/engines.h	
Qudit quantum engines	. 372
experimental/experimental.h	
Experimental/test functions/classes	. 386
nternal/util.h	
Internal utility functions	. 395
nternal/classes/iomanip.h	
Input/output manipulators	. 394
nternal/classes/singleton.h	
Singleton pattern via CRTP	. 395
MATLAB/matlab.h	
Input/output interfacing with MATLAB	. 397

# **Chapter 6**

# **Namespace Documentation**

# 6.1 qpp Namespace Reference

Quantum++ main namespace.

# **Namespaces**

· exception

Quantum++ exception hierarchy namespace.

· experimental

Experimental/test functions/classes, do not use or modify.

internal

Internal utility functions, do not use them directly or modify them.

literals

# Classes

• class Bit\_circuit

Classical reversible circuit simulator.

• class Codes

const Singleton class that defines quantum error correcting codes

· class Dynamic\_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime.

· class Gates

const Singleton class that implements most commonly used gates

class IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

class IJSON

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

class Init

const Singleton class that performs additional initializations/cleanups

· struct is complex

Checks whether the type is a complex type.

• struct is\_complex< std::complex< T > >

Checks whether the type is a complex number type, specialization for complex types.

· struct is\_iterable

Checks whether T is compatible with an STL-like iterable container.

 $\bullet \ \ struct\ is\_iterable < T,\ to\_void < \ decltype(std::declval < T>().begin()),\ decltype(std::declval < T>().end()),\ decltype(*(std::declval < T>().end())),\ decltype(*(std::declval < T>().end()$ 

Checks whether T is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

• struct is\_matrix\_expression

Checks whether the type is an Eigen matrix expression.

· struct make void

Helper for qpp::to\_void<> alias template.

· class NoiseBase

Base class for all noise models, derive your particular noise model.

class NoiseType

Contains template tags used to specify the noise type.

class QCircuit

Quantum circuit description.

class QEngine

Quantum circuit engine, executes qpp::QCircuit.

class QNoisyEngine

Noisy quantum circuit engine, executes qpp::QCircuit.

· class QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

• class QubitBitFlipNoise

Qubit bit flip noise.

· class QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

· class QubitDepolarizingNoise

Qubit depolarizing noise.

• class QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

· class QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

· class QuditDepolarizingNoise

Qudit depolarizing noise.

· class RandomDevices

Singleton class that manages the source of randomness in the library.

· class States

const Singleton class that implements most commonly used states

class Timer

Chronometer.

## **Typedefs**

```
    template<typename... Ts>
        using to_void = typename make_void< Ts... >::type
```

Alias template that implements the proposal for void\_t.

using idx = std::size\_t

Non-negative integer index, make sure you use an unsigned type.

• using bigint = long long int

Big integer.

• using cplx = std::complex< double >

Complex number in double precision.

• using ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector.

• using bra = Eigen::RowVectorXcd

Complex (double precision) dynamic Eigen row vector.

using cmat = Eigen::MatrixXcd

Complex (double precision) dynamic Eigen matrix.

using dmat = Eigen::MatrixXd

Real (double precision) dynamic Eigen matrix.

• template<typename Scalar >

```
using dyn_mat = Eigen::Matrix < Scalar, Eigen::Dynamic, Eigen::Dynamic >
```

Dynamic Eigen matrix over the field specified by Scalar.

• template<typename Scalar >

```
using dyn_col_vect = Eigen::Matrix < Scalar, Eigen::Dynamic, 1 >
```

Dynamic Eigen column vector over the field specified by Scalar.

template<typename Scalar >

```
using dyn_row_vect = Eigen::Matrix < Scalar, 1, Eigen::Dynamic >
```

Dynamic Eigen row vector over the field specified by Scalar.

### **Enumerations**

• enum { RES, PROB, ST }

Constants to be used by std::get<> on the result of qpp::measure(), qpp\_measure\_seq() etc.

# **Functions**

cplx omega (idx D)

D-th root of unity.

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$ 

dyn\_col\_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx >
&dims)

Schmidt coefficients of the bi-partite pure state A.

• template<typename Derived >

```
dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2)
```

Schmidt coefficients of the bi-partite pure state A.

template<typename Derived >

```
cmat schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
```

Schmidt basis on Alice side.

template<typename Derived >

```
cmat schmidtA (const Eigen::MatrixBase< Derived > &A, idx d=2)
```

Schmidt basis on Alice side.

template<typename Derived >

```
cmat schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
```

Schmidt basis on Bob side.

template<typename Derived >

```
cmat schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2)
```

Schmidt basis on Bob side.

• template<typename Derived >

std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)

Schmidt probabilities of the bi-partite pure state A.

```
• template<typename Derived >
  std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt probabilities of the bi-partite pure state A.

    template<typename Derived >

  double entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Entanglement of the bi-partite pure state A.

    template<typename Derived >

  double entanglement (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Entanglement of the bi-partite pure state A.
• template<typename Derived >
  double gconcurrence (const Eigen::MatrixBase< Derived > &A)
      G-concurrence of the bi-partite pure state A.

    template < typename Derived >

  double negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double negativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Logarithmic negativity of the bi-partite mixed state A.
• template<typename Derived >
  double lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double concurrence (const Eigen::MatrixBase< Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.

    template<typename Derived >

  double entropy (const Eigen::MatrixBase< Derived > &A)
      von-Neumann entropy of the density matrix A

    double entropy (const std::vector< double > &prob)

      Shannon entropy of the probability distribution prob.

    template<typename Derived >

  double renyi (const Eigen::MatrixBase< Derived > &A, double alpha)
      Renyi- \alpha entropy of the density matrix A, for \alpha \geq 0.

    double renyi (const std::vector< double > &prob, double alpha)

      Renyi- \alpha entropy of the probability distribution prob, for \alpha > 0.
• template<typename Derived >
  double tsallis (const Eigen::MatrixBase< Derived > &A, double q)
      Tsallis- q entropy of the density matrix A, for q \geq 0.

    double tsallis (const std::vector< double > &prob, double q)

      Tsallis- q entropy of the probability distribution prob, for q \geq 0.
• template<typename Derived >
  double qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx > &subsysB, const std::vector< idx > &dims)
      Quantum mutual information between 2 subsystems of a composite system.

    template<typename Derived >

  \label{eq:const_decomposition} \mbox{double } \mbox{qmutualinfo} \mbox{ (const Eigen::MatrixBase} < \mbox{Derived} > \&\mbox{A, const std::vector} < \mbox{idx} > \&\mbox{subsysA, const}
  std::vector< idx > &subsysB, idx d=2)
      Quantum mutual information between 2 subsystems of a composite system.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > transpose (const Eigen::MatrixBase< Derived > &A)
      Transpose.
```

```
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > conjugate (const Eigen::MatrixBase< Derived > &A)
     Complex conjugate.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > adjoint (const Eigen::MatrixBase< Derived > &A)
     Adjoint.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > inverse (const Eigen::MatrixBase< Derived > &A)
      Inverse.
\bullet \ \ {\it template}{<} {\it typename Derived}>
  Derived::Scalar trace (const Eigen::MatrixBase< Derived > &A)
      Trace.

    template<typename Derived >

  Derived::Scalar det (const Eigen::MatrixBase< Derived > &A)
     Determinant.
• template<typename Derived >
  Derived::Scalar logdet (const Eigen::MatrixBase< Derived > &A)
     Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar sum (const Eigen::MatrixBase< Derived > &A)
      Element-wise sum of A.

    template<typename Derived >

  Derived::Scalar prod (const Eigen::MatrixBase< Derived > &A)
     Element-wise product of A.

    template<typename Derived >

  double norm (const Eigen::MatrixBase< Derived > &A)
     Frobenius norm.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > normalize (const Eigen::MatrixBase< Derived > &A)
     Normalizes state vector (column or row vector) or density matrix.

    template<typename Derived >

  std::pair< dyn_col_vect< cplx >, cmat > eig (const Eigen::MatrixBase< Derived > &A)
     Full eigen decomposition.

    template<typename Derived >

  dyn_col_vect< cplx > evals (const Eigen::MatrixBase< Derived > &A)
     Eigenvalues.

    template<typename Derived >

  cmat evects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors.

    template<typename Derived >

  std::pair< dyn col vect< double >, cmat > heig (const Eigen::MatrixBase< Derived > &A)
     Full eigen decomposition of Hermitian expression.
• template<typename Derived >
  dyn_col_vect< double > hevals (const Eigen::MatrixBase< Derived > &A)
     Hermitian eigenvalues.

    template<typename Derived >

  cmat hevects (const Eigen::MatrixBase< Derived > &A)
      Eigenvectors of Hermitian matrix.
• template<typename Derived >
  std::tuple < cmat, dyn col vect < double >, cmat > svd (const Eigen::MatrixBase < Derived > &A)
     Full singular value decomposition.

    template<typename Derived >

  dyn_col_vect< double > svals (const Eigen::MatrixBase< Derived > &A)
```

Kronecker product.

```
Singular values.
• template<typename Derived >
  cmat svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.
• template<typename Derived >
  cmat svdV (const Eigen::MatrixBase< Derived > &A)
     Right singular vectors.
• template<typename Derived >
  cmat funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)
template<typename Derived >
  cmat sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.

    template<typename Derived >

  cmat absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.
• template<typename Derived >
  cmat expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.

    template<typename Derived >

  cmat logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.

    template<typename Derived >

  cmat sinm (const Eigen::MatrixBase< Derived > &A)
• template<typename Derived >
  cmat cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.

    template<typename Derived >

  cmat spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > powm (const Eigen::MatrixBase< Derived > &A, idx n)
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.
• template<typename Derived >
  double schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const type-
  name Derived::Scalar &))
     Functor.
template<typename T >
  dyn_mat< typename T::Scalar > kron (const T &head)
     Kronecker product.

    template<typename T, typename... Args>

  dyn_mat< typename T::Scalar > kron (const T &head, const Args &... tail)
     Kronecker product.
template<typename Derived >
  dyn_mat< typename Derived::Scalar > kron (const std::vector< Derived > &As)
     Kronecker product.
template<typename Derived >
  dyn mat< typename Derived::Scalar > kron (const std::initializer list< Derived > &As)
```

```
    template<typename Derived >

  dyn_mat< typename Derived::Scalar > kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Kronecker power.
template<typename T >
  dyn mat< typename T::Scalar > dirsum (const T &head)
     Direct sum.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > dirsum (const T &head, const Args &... tail)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > dirsum (const std::vector< Derived > &As)
     Direct sum.
• template<typename Derived >
  dyn mat< typename Derived::Scalar > dirsum (const std::initializer list< Derived > &As)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > reshape (const Eigen::MatrixBase< Derived > &A, idx rows, idx
  cols)
     Reshape.

    template<typename Derived1 , typename Derived2 >

  dyn mat< typename Derived1::Scalar > comm (const Eigen::MatrixBase< Derived1 > &A, const Eigen::↔
  MatrixBase< Derived2 > &B)
     Commutator.
- template<typename Derived1 , typename Derived2 >
  dyn_mat< typename Derived1::Scalar > anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > prj (const Eigen::MatrixBase< Derived > &A)
     Projector.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > grams (const std::vector< Derived > &As)
     Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > grams (const std::initializer_list< Derived > &As)
     Gram-Schmidt orthogonalization.

    template < typename Derived >

  dyn_mat< typename Derived::Scalar > grams (const Eigen::MatrixBase< Derived > &A)
     Gram-Schmidt orthogonalization.

    std::vector< idx > n2multiidx (idx n, const std::vector< idx > &dims)

     Non-negative integer index to multi-index.

    idx multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

     Multi-index to non-negative integer index.

    ket mket (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Multi-partite qudit ket.

    ket mket (const std::vector < idx > &mask, idx d=2)

     Multi-partite qudit ket.

    cmat mprj (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Projector onto multi-partite qudit ket.

    cmat mprj (const std::vector< idx > &mask, idx d=2)
```

Projector onto multi-partite qudit ket.

• template<typename InputIterator >

```
std::vector< double > abssq (InputIterator first, InputIterator last)
```

Computes the absolute values squared of an STL-like range of complex numbers.

template<typename Container >

```
std::vector< double > abssq (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)
```

Computes the absolute values squared of an STL-like container.

template<typename Derived >

```
std::vector< double > abssq (const Eigen::MatrixBase< Derived > &A)
```

Computes the absolute values squared of an Eigen expression.

• template<typename InputIterator >

```
std::iterator_traits< InputIterator >::value_type sum (InputIterator first, InputIterator last)
```

Element-wise sum of an STL-like range.

• template<typename Container >

```
Container::value_type sum (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)
```

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

```
std::iterator traits < InputIterator >::value type prod (InputIterator first, InputIterator last)
```

Element-wise product of an STL-like range.

template<typename Container >

Container::value\_type prod (const Container &c, typename std::enable\_if< is\_iterable< Container >::value >::type \*=nullptr)

Element-wise product of the elements of an STL-like container.

template<typename Derived >

```
dyn col vect< typename Derived::Scalar > rho2pure (const Eigen::MatrixBase< Derived > &A)
```

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

std::vector< idx > complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

• template<typename Derived >

```
std::vector< double > rho2bloch (const Eigen::MatrixBase< Derived > &A)
```

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

• template<typename Derived >

```
std::size_t hash_eigen (const Eigen::MatrixBase< Derived > &A, std::size_t seed=0)
```

Computes the hash of en Eigen matrix/vector/expression.

• template<typename Derived >

```
internal::IOManipEigen disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
```

Eigen expression ostream manipulator.

internal::IOManipEigen disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

 $\bullet \ \ \text{template}{<} \text{typename InputIterator} >$ 

internal::IOManipRange< InputIterator > disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)

Range ostream manipulator.

• template<typename Container >

internal::IOManipRange< typename Container::const\_iterator > disp (const Container &c, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop, typename std⇔ ::enable if< is iterable< Container >::value >::type \*=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

template<typename PointerType >
 internal::IOManipPointer< PointerType > disp (const PointerType \*p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)

C-style pointer ostream manipulator.

• template<typename Derived >

void save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.

• template<typename Derived >

dyn\_col\_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)

Generalized inner product.

template<typename Derived >

dyn\_col\_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer\_list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

• template<typename Derived >

std::tuple < idx, std::vector < cmat >> measure (const Eigen::MatrixBase < Derived > &A, const std::vector < cmat > &Ks, const std::vector < idx > &target, const std::vector < idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer\_list< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple < idx, std::vector < cmat >> measure (const Eigen::MatrixBase < Derived > &A, const std::vector < cmat > &Ks, const std::vector < idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer\_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

template<typename Derived >

std::tuple < idx, std::vector < double >, std::vector < cmat > > measure (const Eigen::MatrixBase < Derived > &A, const cmat &V, const std::vector < idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > measure\_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template<typename Derived >

std::tuple< std::vector< idx >, double, cmat > measure\_seq (const Eigen::MatrixBase< Derived > &A, std::vector< idx > target, idx d=2)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template < typename Derived >

std::enable\_if< std::is\_same< typename Derived::Scalar, cplx >::value, dyn\_mat< cplx > >::type loadMATLAB (const std::string &mat\_file, const std::string &var\_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable\_if<!std::is\_same< typename Derived::Scalar, cplx >::value, dyn\_mat< typename Derived::

Scalar > >::type loadMATLAB (const std::string &mat file, const std::string &var name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >

std::enable\_if< std::is\_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat\_file, const std::string &var\_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

• template<typename Derived >

std::enable\_if< !std::is\_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat\_file, const std::string &var\_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

std::vector< int > x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

• bigint gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > invperm (const std::vector< idx > &perm)

Inverse permutation.

• std::vector< idx > compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

std::vector< bigint > factors (bigint a)

Prime factor decomposition.

• bigint modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

bigint modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple < bigint, bigint, bigint > egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

• bigint modiny (bigint a, bigint p)

Modular inverse of a mod p.

bool isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

bigint randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

- std::vector < std::pair < int, int > > convergents (const std::vector < int > &cf)

Convergents.

std::vector< std::pair< int, int > > convergents (double x, idx N)

Convergents.

• template<typename Derived1 , typename Derived2 >

dyn\_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, const
std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn\_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, idx
d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)
```

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, const std::vector< idx > &dims)
```

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, idx d=2)
```

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat kraus2super (const std::vector< cmat > &Ks)

Superoperator matrix.

cmat kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector < cmat > choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

 $\bullet \ \ \mathsf{template}{<}\mathsf{typename} \ \mathsf{Derived}>$ 

```
\label{lem:dyn_mat}  \mbox{dyn\_mat} < \mbox{typename Derived::Scalar} > \mbox{ptrace1} \mbox{ (const Eigen::MatrixBase} < \mbox{Derived} > \mbox{\&A, const std} \\ \mbox{::vector} < \mbox{idx} > \mbox{\&dims})
```

Partial trace.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector < idx > &dims)

Partial trace.

• template<typename Derived >

dyn mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector<
idx > &target, const std::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector
idx > &target, idx d=2)

Partial trace.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > ptranspose (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, const std::vector< idx > &dims)

Partial transpose.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > ptranspose (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial transpose.

• template<typename Derived >

Subsystem permutation.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > syspermute (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &perm, idx d=2)

Subsystem permutation.

• template<typename Derived >

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > applyTFQ (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2, bool swap=true)

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived>

dyn\_col\_vect< typename Derived::Scalar > TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

template<typename Derived >

dyn\_col\_vect< typename Derived::Scalar > QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Qudit quantum Fourier transform.

double rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

• bigint rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx randidx (idx a=std::numeric\_limits< idx >::min(), idx b=std::numeric\_limits< idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

template<typename Derived >

Derived rand (idx rows QPP\_UNUSED\_, idx cols QPP\_UNUSED\_, double a QPP\_UNUSED\_=0, double b QPP\_UNUSED =1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

• template<>

```
dmat rand (idx rows, idx cols, double a, double b)
```

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

template<>

```
cmat rand (idx rows, idx cols, double a, double b)
```

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

• template<typename Derived >

Derived randn (idx rows QPP\_UNUSED\_, idx cols QPP\_UNUSED\_, double mean QPP\_UNUSED\_=0, double sigma QPP\_UNUSED\_=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

```
dmat randn (idx rows, idx cols, double mean, double sigma)
```

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

template<>

```
cmat randn (idx rows, idx cols, double mean, double sigma)
```

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

• double randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

• cmat randU (idx D=2)

Generates a random unitary matrix.

· cmat randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat randH (idx D=2)

Generates a random Hermitian matrix.

ket randket (idx D=2)

Generates a random normalized ket (pure state vector)

cmat randrho (idx D=2)

Generates a random density matrix.

std::vector < idx > randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.

std::vector< double > uniform (idx N)

Uniform probability distribution vector.

std::vector< double > marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > marginalY (const dmat &probXY)

Marginal distribution.

template<typename Container >
 double avg (const std::vector< double > &prob, const Container &X, typename std::enable\_if< is\_iterable<
 Container >::value >::type \*=nullptr)

Average.

• template<typename Container >

double cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable\_if< is\_iterable< Container >::value >::type \*=nullptr)

Covariance.

• template<typename Container >

double var (const std::vector< double > &prob, const Container &X, typename std::enable\_if< is\_iterable< Container >::value >::type \*=nullptr)

Variance.

• template<typename Container >

double sigma (const std::vector< double > &prob, const Container &X, typename std::enable\_if< is\_iterable< Container >::value >::type \*=nullptr)

Standard deviation.

• template<typename Container >

double cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable\_if< is\_iterable< Container >::value >::type \*=nullptr)

Correlation.

#### **Variables**

constexpr double chop = 1e-16

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

• constexpr idx maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

constexpr double pi = 3.141592653589793238462643383279502884

 $\pi$ 

constexpr double ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

constexpr double infty = std::numeric\_limits<double>::max()

Used to denote infinity in double precision.

# 6.1.1 Detailed Description

Quantum++ main namespace.

## 6.1.2 Typedef Documentation

#### 6.1.2.1 bigint

```
using qpp::bigint = typedef long long int
```

# Big integer.

```
6.1.2.2 bra
```

```
using qpp::bra = typedef Eigen::RowVectorXcd
```

Complex (double precision) dynamic Eigen row vector.

### 6.1.2.3 cmat

```
using qpp::cmat = typedef Eigen::MatrixXcd
```

Complex (double precision) dynamic Eigen matrix.

# 6.1.2.4 cplx

```
using qpp::cplx = typedef std::complex<double>
```

Complex number in double precision.

# 6.1.2.5 dmat

```
using qpp::dmat = typedef Eigen::MatrixXd
```

Real (double precision) dynamic Eigen matrix.

# 6.1.2.6 dyn\_col\_vect

```
template<typename Scalar >
using qpp::dyn_col_vect = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, 1>
```

Dynamic Eigen column vector over the field specified by Scalar.

### Example:

```
// type of colvect is Eigen::Matrix<float, Eigen::Dynamic, 1>
dyn_col_vect<float> colvect(2);
```

```
6.1.2.7 dyn_mat
```

```
template<typename Scalar >
using qpp::dyn_mat = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, Eigen::Dynamic>
```

Dynamic Eigen matrix over the field specified by Scalar.

#### Example:

```
// type of mat is Eigen::Matrix<float, Eigen::Dynamic, Eigen::Dynamic>
dyn_mat<float> mat(2, 3);
```

### 6.1.2.8 dyn\_row\_vect

```
template<typename Scalar >
using qpp::dyn_row_vect = typedef Eigen::Matrix<Scalar, 1, Eigen::Dynamic>
```

Dynamic Eigen row vector over the field specified by Scalar.

#### Example:

```
// type of rowvect is Eigen::Matrix<float, 1, Eigen::Dynamic>
dyn_row_vect<float> rowvect(3);
```

### 6.1.2.9 idx

```
using qpp::idx = typedef std::size_t
```

Non-negative integer index, make sure you use an unsigned type.

#### 6.1.2.10 ket

```
using qpp::ket = typedef Eigen::VectorXcd
```

Complex (double precision) dynamic Eigen column vector.

# 6.1.2.11 to\_void

```
template<typename... Ts>
using qpp::to_void = typedef typename make_void<Ts...>::type
```

Alias template that implements the proposal for  $void_t$ .

See also

```
http://www.open-std.org/jtc1/sc22/wg21/docs/papers/2014/n3911
```

# 6.1.3 Enumeration Type Documentation

# 6.1.3.1 anonymous enum

```
anonymous enum
```

Constants to be used by std::get<> on the result of qpp::measure(), qpp\_measure\_seq() etc.

### Enumerator

RES	Measurement result(s)
PROB	Probabilit(y)/(ies)
ST	Output state(s)

# 6.1.4 Function Documentation

### 6.1.4.1 absm()

Matrix absolute value.

#### **Parameters**

```
A Eigen expression
```

# Returns

Matrix absolute value of A

# 6.1.4.2 abssq() [1/3]

Computes the absolute values squared of an STL-like range of complex numbers.

### **Parameters**

first	Iterator to the first element of the range
last	Iterator to the last element of the range

### Returns

Real vector consisting of the range absolute values squared

Computes the absolute values squared of an STL-like container.

#### **Parameters**

```
c STL-like container
```

### Returns

Real vector consisting of the container's absolute values squared

Computes the absolute values squared of an Eigen expression.

## **Parameters**

```
A Eigen expression
```

# Returns

Real vector consisting of the absolute values squared

# 6.1.4.5 adjoint()

# Adjoint.

```
A Eigen expression
```

Adjoint (Hermitian conjugate) of A, as a dynamic matrix over the same scalar field as A

### 6.1.4.6 anticomm()

Anti-commutator.

### See also

qpp::comm()

Anti-commutator  $\{A,B\}=AB+BA$ . Both A and B must be Eigen expressions over the same scalar field.

# **Parameters**

Α	Eigen expression
В	Eigen expression

# Returns

Anti-commutator AB + BA, as a dynamic matrix over the same scalar field as A

# **6.1.4.7** apply() [1/5]

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

# Note

The dimension of the gate A must match the dimension of target

state	Eigen expression
Α	Eigen expression
Gataligaeti k	y Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

Gate A applied to the part target of state

```
6.1.4.8 apply() [2/5]
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

# **Parameters**

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

# Returns

Gate A applied to the part target of state

```
6.1.4.9 apply() [3/5]
```

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

Α	Eigen expression
Ks	Set of Kraus operators

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*.

#### **Parameters**

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes where the Kraus operators Ks are applied
dims	Dimensions of the multi-partite system

# Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*.

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes where the Kraus operators Ks are applied
d	Subsystem dimensions

Output density matrix after the action of the channel

# 6.1.4.12 applyCTRL() [1/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

#### See also

```
qpp::Gates::CTRL()
```

### Note

The dimension of the gate A must match the dimension of *target*. Also, all control subsystems in *ctrl* must have the same dimension.

# **Parameters**

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

# Returns

CTRL-A gate applied to the part target of state

## 6.1.4.13 applyCTRL() [2/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

### See also

```
qpp::Gates::CTRL()
```

#### Note

The dimension of the gate A must match the dimension of target

#### **Parameters**

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

### Returns

CTRL-A gate applied to the part target of state

# 6.1.4.14 applyQFT()

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

#### **Parameters**

Α	Eigen expression
target	Subsystem indexes where the QFT is applied
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

# Returns

Qudit Quantum Fourier transform applied to the part target of A

# 6.1.4.15 applyTFQ()

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::applyTFQ (
```

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & target,
idx d = 2,
bool swap = true )
```

Applies the inverse (adjoint) qudit quantum Fourier transform to the part *target* of the multi-partite state vector or density matrix *A*.

### **Parameters**

Α	Eigen expression
target	Subsystem indexes where the TFQ is applied
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

### Returns

Inverse (adjoint) qudit Quantum Fourier transform applied to the part target of A

### 6.1.4.16 avg()

# Average.

# **Parameters**

pro	b	Real probability vector representing the probability distribution of $X$
X		Real random variable values represented by an STL-like container

# Returns

Average of X

# 6.1.4.17 bloch2rho()

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

# See also

qpp::rho2bloch()

r 3-dimensional real vector

### Returns

Qubit density matrix

# 6.1.4.18 choi2kraus()

Orthogonal Kraus operators from Choi matrix.

#### See also

qpp::kraus2choi()

Extracts a set of orthogonal (under Hilbert-Schmidt operator norm) Kraus operators from the Choi matrix A

Note

The Kraus operators satisfy  $Tr(K_i^\dagger K_j) = \delta_{ij}$  for all  $i \neq j$ 

## **Parameters**

A Choi matrix

## Returns

Set of orthogonal Kraus operators

# 6.1.4.19 choi2super()

Converts Choi matrix to superoperator matrix.

# See also

qpp::super2choi()

```
A Choi matrix
```

# Returns

Superoperator matrix

# 6.1.4.20 comm()

Commutator.

#### See also

qpp::anticomm()

Commutator [A, B] = AB - BA. Both A and B must be Eigen expressions over the same scalar field.

# **Parameters**

Α	Eigen expression
В	Eigen expression

# Returns

Commutator AB-BA, as a dynamic matrix over the same scalar field as  ${\it A}$ 

# 6.1.4.21 complement()

```
std::vector<idx> qpp::complement (
    std::vector< idx > subsys,
    idx n ) [inline]
```

Constructs the complement of a subsystem vector.

subsys	Subsystem vector
n	Total number of systems

Complement of *subsys* with respect to the set  $\{0, 1, \dots, n-1\}$ 

# 6.1.4.22 compperm()

Compose permutations.

### **Parameters**

perm	Permutation
sigma	Permutation

### Returns

Composition of the permutations  $perm \circ sigma = perm(sigma)$ 

# 6.1.4.23 concurrence()

Wootters concurrence of the bi-partite qubit mixed state A.

### **Parameters**

```
A Eigen expression
```

# Returns

Wootters concurrence

# 6.1.4.24 conjugate()

Complex conjugate.

A Eigen expression

# Returns

Complex conjugate of A, as a dynamic matrix over the same scalar field as A

### 6.1.4.25 contfrac2x()

```
double qpp::contfrac2x ( const std::vector< int > & cf, idx N = idx(-1) ) [inline]
```

Real representation of a simple continued fraction.

#### See also

qpp::x2contfrac()

### Note

If N is greater than the size of cf (by default it is), then all terms in cf are considered.

# **Parameters**

cf	Integer vector containing the simple continued fraction expans	
Ν	Number of terms considered in the continued fraction expansion.	

### Returns

Real representation of the simple continued fraction

# **6.1.4.26** convergents() [1/2]

```
std::vector<std::pair<int, int> > qpp::convergents ( const std::vector< int > & cf ) [inline]
```

# Convergents.

# See also

qpp::contfrac2x() and qpp::x2contfrac()

```
cf Continued fraction
```

# Returns

Vector of convergents pairs  $(a_k, b_k)$  that approximate the number represented by the continued fraction

# **6.1.4.27** convergents() [2/2]

```
std::vector<std::pair<int, int> > qpp::convergents ( double x, idx N) [inline]
```

# Convergents.

### See also

```
qpp::contfrac2x() and qpp::x2contfrac()
```

### Note

In the continued fraction expansion of x has less terms than N, then the series of convergents is truncated to the number of terms in the continued fraction expansion of x.

# **Parameters**

Χ	Real number
Ν	Number of convergents.

# Returns

Vector of convergents pairs  $(a_k, b_k)$  that approximate the number x

### 6.1.4.28 cor()

#### Correlation.

probXY	Real matrix representing the joint probability distribution of $X$ and $Y$ in lexicographical order ( $X$ labels the rows, $Y$ labels the columns)
Χ	Real random variable values represented by an STL-like container
Y	Real random variable values represented by an STL-like container

# Returns

Correlation of X and Y

# 6.1.4.29 cosm()

### Matrix cos.

### **Parameters**

```
A Eigen expression
```

### Returns

Matrix cosine of A

# 6.1.4.30 cov()

## Covariance.

probXY	Real matrix representing the joint probability distribution of $X$ and $Y$ in lexicographical order ( $X$ labels the rows, $Y$ labels the columns)
Χ	Real random variable values represented by an STL-like container
Υ	Real random variable values represented by an STL-like container

Covariance of X and Y

### 6.1.4.31 cwise()

### Functor.

#### **Parameters**

Α	Eigen expression
f	Pointer-to-function from scalars of A to OutputScalar

### Returns

Component-wise f(A), as a dynamic matrix over the *OutputScalar* scalar field

## 6.1.4.32 det()

### Determinant.

## **Parameters**

```
A Eigen expression
```

## Returns

Determinant of A, as a scalar over the same scalar field as A. Returns  $\pm \infty$  when the determinant overflows/underflows.

# Direct sum.

### See also

qpp::dirsumpow()

Used to stop the recursion for the variadic template version of qpp::dirsum()

### **Parameters**

```
head Eigen expression
```

### Returns

Its argument head

### **6.1.4.34** dirsum() [2/4]

Direct sum.

### See also

qpp::dirsumpow()

### **Parameters**

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

## Returns

Direct sum of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

# **6.1.4.35** dirsum() [3/4]

Direct sum.

## See also

qpp::dirsumpow()

As std::vector of Eigen expressions

### Returns

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

#### See also

qpp::dirsumpow()

#### **Parameters**

As std::initializer\_list of Eigen expressions, such as {A1, A2, ..., Ak}

## Returns

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

### 6.1.4.37 dirsumpow()

Direct sum power.

# See also

qpp::dirsum()

Α	Eigen expression
n	Non-negative integer

### Returns

Direct sum of A with itself n times  $A^{\oplus n}$ , as a dynamic matrix over the same scalar field as A

Eigen expression ostream manipulator.

### **Parameters**

Α	Eigen expression
chop	Set to zero the elements smaller in absolute value than chop

## Returns

Instance of qpp::internal::IOManipEigen

Complex number ostream manipulator.

# **Parameters**

Z	Complex number (or any other type implicitly cast-able to std::complex <double>)</double>
chop	Set to zero the elements smaller in absolute value than chop

# Returns

Instance of qpp::internal::IOManipEigen

Range ostream manipulator.

#### **Parameters**

first	Iterator to the first element of the range
last	Iterator to the last element of the range
separator	Separator
start	Left marking
end	Right marking
chop	Set to zero the elements smaller in absolute value than chop

### Returns

Instance of qpp::internal::IOManipRange

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

С	Container
separator	Separator
start	Left marking
end	Right marking
chop	Set to zero the elements smaller in absolute value than chop

Instance of qpp::internal::IOManipRange

C-style pointer ostream manipulator.

### **Parameters**

р	Pointer to the first element
N	Number of elements to be displayed
separator	Separator
start	Left marking
end	Right marking
chop	Set to zero the elements smaller in absolute value than chop

#### Returns

Instance of qpp::internal::IOManipPointer

# 6.1.4.43 egcd()

Extended greatest common divisor of two integers.

# See also

qpp::gcd()

а	Integer
b	Integer

Tuple of: 1. Integer m, 2. Integer n, and 3. Non-negative integer gcd(a,b) such that ma + nb = gcd(a,b)

# 6.1.4.44 eig()

Full eigen decomposition.

See also

qpp::heig()

#### **Parameters**

```
A Eigen expression
```

### Returns

Pair of: 1. Eigenvalues of A, as a complex dynamic column vector, and 2. Eigenvectors of A, as columns of a complex dynamic matrix

### 6.1.4.45 entanglement() [1/2]

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

# See also

qpp::entropy()

Α	Eigen expression
dims	Dimensions of the bi-partite system

Entanglement, with the logarithm in base 2

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

### See also

qpp::entropy()

#### **Parameters**

Α	Eigen expression
d	Subsystem dimensions

# Returns

Entanglement, with the logarithm in base 2

von-Neumann entropy of the density matrix A

# **Parameters**

```
A Eigen expression
```

### Returns

von-Neumann entropy, with the logarithm in base 2

Shannon entropy of the probability distribution prob.

**Parameters** 

```
prob Real probability vector
```

Returns

Shannon entropy, with the logarithm in base 2

### 6.1.4.49 evals()

Eigenvalues.

See also

qpp::hevals()

**Parameters** 

```
A Eigen expression
```

Returns

Eigenvalues of A, as a complex dynamic column vector

## 6.1.4.50 evects()

Eigenvectors.

See also

qpp::hevects()

A Eigen expression

### Returns

Eigenvectors of A, as columns of a complex dynamic matrix

# 6.1.4.51 expm()

Matrix exponential.

### **Parameters**

A Eigen expression

### Returns

Matrix exponential of A

# 6.1.4.52 factors()

Prime factor decomposition.

Note

Runs in  $\mathcal{O}(\sqrt{n})$  time complexity

### **Parameters**

a Integer different from 0, 1 or -1

## Returns

Integer vector containing the factors

### 6.1.4.53 funm()

Functional calculus f(A)

### **Parameters**

Α	Eigen expression
f	Pointer-to-function from complex to complex

# Returns

f(A)

Greatest common divisor of two integers.

## See also

qpp::lcm()

# Parameters

а	Integer
b	Integer

## Returns

Greatest common divisor of a and b

Greatest common divisor of a list of integers.

See also

```
qpp::lcm()
```

**Parameters** 

```
as List of integers
```

Returns

Greatest common divisor of all numbers in as

# 6.1.4.56 gconcurrence()

G-concurrence of the bi-partite pure state A.

Note

Both local dimensions must be equal

Uses qpp::logdet() to avoid overflows

See also

```
qpp::logdet()
```

**Parameters** 

```
A Eigen expression
```

Returns

G-concurrence

```
6.1.4.57 grams() [1/3]
```

Gram-Schmidt orthogonalization.

As std::vector of Eigen expressions as column vectors

### Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

Gram-Schmidt orthogonalization.

### **Parameters**

As std::initializer\_list of Eigen expressions as column vectors

### Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

Gram-Schmidt orthogonalization.

#### **Parameters**

A Eigen expression, the input vectors are the columns of A

### Returns

Gram-Schmidt vectors of the columns of A, as columns of a dynamic matrix over the same scalar field as A

### 6.1.4.60 hash\_eigen()

Computes the hash of en Eigen matrix/vector/expression.

### Note

Code taken from boost::hash\_combine(), see https://www.boost.org/doc/libs/1\_69\_← 0/doc/html/hash/reference.html#boost.hash\_combine

#### **Parameters**

Α	Eigen expression	
seed	Seed, 0 by default	

#### Returns

Hash of its argument

## 6.1.4.61 heig()

Full eigen decomposition of Hermitian expression.

### See also

qpp::eig()

## **Parameters**

A Eigen expression

## Returns

Pair of: 1. Eigenvalues of A, as a real dynamic column vector, and 2. Eigenvectors of A, as columns of a complex dynamic matrix

### 6.1.4.62 hevals()

Hermitian eigenvalues.

See also

qpp::evals()

### **Parameters**

A Eigen expression

### Returns

Eigenvalues of Hermitian A, as a real dynamic column vector

### 6.1.4.63 hevects()

Eigenvectors of Hermitian matrix.

See also

qpp::evects()

#### **Parameters**

A Eigen expression

# Returns

Eigenvectors of Hermitian matrix A, as columns of a complex matrix

### 6.1.4.64 inverse()

Inverse.

```
A Eigen expression
```

### Returns

Inverse of A, as a dynamic matrix over the same scalar field as A

### 6.1.4.65 invperm()

```
std::vector<idx> qpp::invperm ( const std::vector< idx > & perm ) [inline]
```

Inverse permutation.

### **Parameters**

perm	Permutation
------	-------------

#### Returns

Inverse of the permutation perm

### **6.1.4.66** ip() [1/2]

Generalized inner product.

## **Parameters**

phi	Column vector Eigen expression
psi	Column vector Eigen expression
subsys	Subsystem indexes over which phi is defined
dims	Dimensions of the multi-partite system

## Returns

Inner product  $\langle \phi_{subsys} | \psi \rangle$  , as a scalar or column vector over the remaining Hilbert space

Generalized inner product.

### **Parameters**

phi	Column vector Eigen expression
psi	Column vector Eigen expression
subsys	Subsystem indexes over which phi is defined
d	Subsystem dimensions

### Returns

Inner product  $\langle \phi_{subsys} | \psi \rangle$ , as a scalar or column vector over the remaining Hilbert space

## 6.1.4.68 isprime()

```
bool qpp::isprime ( bigint p, idx k = 80 ) [inline]
```

Primality test based on the Miller-Rabin's algorithm.

### **Parameters**

р	Integer different from 0, 1 or -1
k	Number of iterations. The probability of a false positive is $2^{-k}$ .

## Returns

True if the number is (most-likely) prime, false otherwise

# 6.1.4.69 kraus2choi()

Choi matrix.

#### See also

qpp::choi2kraus()

Constructs the Choi matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis  $\{|i\rangle\langle j|\}$  ordered in lexicographical order, i.e.  $|0\rangle\langle 0|$ ,  $|0\rangle\langle 1|$  etc.

Note

The superoperator matrix S and the Choi matrix C are related by  $S_{ab,mn}=C_{ma,nb}$ 

### **Parameters**

```
Ks Set of Kraus operators
```

#### Returns

Choi matrix

# 6.1.4.70 kraus2super()

Superoperator matrix.

Constructs the superoperator matrix of the channel specified by the set of Kraus operators  $\mathit{Ks}$  in the standard operator basis  $\{|i\rangle\langle j|\}$  ordered in lexicographical order, i.e.  $|0\rangle\langle 0|$ ,  $|0\rangle\langle 1|$  etc.

#### **Parameters**

```
Ks Set of Kraus operators
```

# Returns

Superoperator matrix

Kronecker product.

|--|

qpp::kronpow()

Used to stop the recursion for the variadic template version of <a href="app::kron()">app::kron()</a>

head Eigen expression	
-----------------------	--

### Returns

Its argument head

Kronecker product.

#### See also

qpp::kronpow()

### **Parameters**

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

## Returns

Kronecker product of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

# Kronecker product.

### See also

qpp::kronpow()

```
As std::vector of Eigen expressions
```

### Returns

Kronecker product of all elements in *As*, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

### See also

qpp::kronpow()

#### **Parameters**

```
As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}
```

#### Returns

Kronecker product of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

## 6.1.4.75 kronpow()

Kronecker power.

#### See also

qpp::kron()

Α	Eigen expression
n	Non-negative integer

### Returns

Kronecker product of A with itself n times  $A^{\otimes n}$ , as a dynamic matrix over the same scalar field as A

Least common multiple of two integers.

### See also

```
qpp::gcd()
```

### **Parameters**

а	Integer
b	Integer

### Returns

Least common multiple of a and b

Least common multiple of a list of integers.

## See also

```
qpp::gcd()
```

ac	List of integers
as	

Least common multiple of all numbers in as

### 6.1.4.78 load()

Loads Eigen matrix from a binary file (internal format) in double precision.

### See also

```
qpp::save()
```

The template parameter cannot be automatically deduced and must be explicitly provided, depending on the scalar field of the matrix that is being loaded.

### Example:

```
// loads a previously saved Eigen dynamic complex matrix from "input.bin"
cmat mat = load<cmat>("input.bin");
```

#### **Parameters**

```
fname Output file name
```

### 6.1.4.79 loadMATLAB() [1/2]

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

### See also

```
qpp::saveMATLAB()
```

The template parameter cannot be automatically deduced and must be explicitly provided

### Example:

```
// loads a previously saved Eigen ket
// from the MATLAB file "input.mat"
ket psi = loadMATLABket>("input.mat");
```

# **Template Parameters**

Derived Co	omplex Eigen type
------------	-------------------

#### **Parameters**

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be loaded

### Returns

Eigen dynamic matrix

# 6.1.4.80 loadMATLAB() [2/2]

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

### See also

### qpp::saveMATLAB()

The template parameter cannot be automatically deduced and must be explicitly provided

#### Example:

```
// loads a previously saved Eigen dynamic double matrix // from the MATLAB file "input.mat" dmat mat = loadMATLAB
```

# **Template Parameters**

Derived	Non-complex Eigen type
---------	------------------------

### **Parameters**

ĺ	mat_file	MATALB .mat file
	var_name	Variable name in the .mat file representing the matrix to be loaded

### Returns

Eigen dynamic matrix

### 6.1.4.81 logdet()

Logarithm of the determinant.

Useful when the determinant overflows/underflows

#### **Parameters**

```
A Eigen expression
```

### Returns

Logarithm of the determinant of A, as a scalar over the same scalar field as A

# 6.1.4.82 logm()

Matrix logarithm.

### **Parameters**

```
A Eigen expression
```

### Returns

Matrix logarithm of A

# 6.1.4.83 lognegativity() [1/2]

Logarithmic negativity of the bi-partite mixed state A.

## **Parameters**

Α	Eigen expression
alian a	Disconnicuo of the bi secutite exetern
aims	Dimensions of the bi-partite system

Generated by Doxygen

Logarithmic negativity, with the logarithm in base 2

```
6.1.4.84 lognegativity() [2/2] template<typename Derived > double qpp::lognegativity ( const Eigen::MatrixBase< Derived > & A, idx d = 2)
```

Logarithmic negativity of the bi-partite mixed state A.

### **Parameters**

Α	Eigen expression
d	Subsystem dimensions

### Returns

Logarithmic negativity, with the logarithm in base 2

# 6.1.4.85 marginalX()

Marginal distribution.

### **Parameters**

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels
	the rows, Y labels the columns)

# Returns

Real vector consisting of the marginal distribution of X

### 6.1.4.86 marginalY()

Marginal distribution.

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels	1
	the rows, Y labels the columns)	

#### Returns

Real vector consisting of the marginal distribution of Y

Measures the state vector or density operator A using the set of Kraus operators Ks.

#### **Parameters**

Α	Eigen expression
Ks	Set of Kraus operators

### Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

### **6.1.4.88** measure() [2/9]

Measures the state vector or density matrix  $\boldsymbol{A}$  using the set of Kraus operators  $\boldsymbol{Ks}$ .

Α	Eigen expression
Ks	Set of Kraus operators

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

#### **Parameters**

Α	4 Eigen expression	
U	Unitary matrix whose columns represent the measurement basis vectors	]

#### Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

## See also

```
qpp::measure_seq()
```

## Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

### Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

### **6.1.4.91** measure() [5/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

### See also

```
qpp::measure_seq()
```

### Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

# **Parameters**

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

### Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

### **6.1.4.92** measure() [6/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

#### See also

```
qpp::measure_seq()
```

#### Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

#### **Parameters**

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

# Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

### **6.1.4.93** measure() [7/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

#### See also

```
qpp::measure_seq()
```

## Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

### Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

### **6.1.4.94** measure() [8/9]

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

#### See also

```
qpp::measure_seq()
```

#### Note

The dimension of V must match the dimension of target. The measurement is destructive, i.e. the measured subsystems are traced away.

### **Parameters**

Α	Eigen expression	
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors	
target	Subsystem indexes that are measured	
dims	Dimensions of the multi-partite system	

## Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

### **6.1.4.95** measure() [9/9]

Measures the part *target* of the multi-partite state vector or density matrix *A* in the orthonormal basis or rank-1 projectors specified by the columns of the matrix *V*.

#### See also

```
qpp::measure_seq()
```

#### Note

The dimension of *V* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

#### **Parameters**

Α	Eigen expression	
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors	
target	Subsystem indexes that are measured	
d	Subsystem dimensions	

## Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

```
template<typename Derived >
std::tuple<std::vector<idx>, double, cmat> qpp::meas
```

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

### See also

qpp::measure()

6.1.4.96 measure\_seq() [1/2]

Α	Eigen expression
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

### Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

### See also

qpp::measure()

### **Parameters**

Α	Eigen expression
target	Subsystem indexes that are measured
d	Subsystem dimensions

## Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Multi-partite qudit ket.

### See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket  $|\text{mask}\rangle$ , where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

### **Parameters**

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

### Returns

Multi-partite qudit state vector, as a complex dynamic column vector

```
6.1.4.99 mket() [2/2] ket qpp::mket ( const std::vector< idx > & mask, idx d = 2) [inline]
```

Multi-partite qudit ket.

### See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket  $|mask\rangle$ , all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

## Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

## Returns

Multi-partite qudit state vector, as a complex dynamic column vector

# 6.1.4.100 modinv()

Modular inverse of a mod p.

See also

```
qpp::egcd()
```

Note

a and p must be co-prime

### **Parameters**

а	Non-negative integer
р	Non-negative integer

### Returns

```
Modular inverse a^{-1} \mod p
```

### 6.1.4.101 modmul()

```
bigint qpp::modmul (
          bigint a,
          bigint b,
          bigint p) [inline]
```

Modular multiplication without overflow.

Computes  $ab \bmod p$  without overflow

### **Parameters**

а	Integer
b	Integer
р	Positive integer

## Returns

 $ab \bmod p \text{ avoiding overflow}$ 

# 6.1.4.102 modpow()

Fast integer power modulo  $\emph{p}$  based on the SQUARE-AND-MULTIPLY algorithm.

Note

Uses qpp::modmul() that avoids overflows

Computes  $a^n \mod p$ 

### **Parameters**

а	Non-negative integer
n	Non-negative integer
р	Strictly positive integer

#### Returns

```
a^n \bmod p
```

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket  $|mask\rangle$ , where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

### **Parameters**

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

### Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

```
6.1.4.104 mprj() [2/2] cmat qpp::mprj ( const std::vector< idx > \& mask, idx d = 2) [inline]
```

Projector onto multi-partite qudit ket.

#### See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket  $|mask\rangle$ , all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

#### **Parameters**

mask	std::vector of non-negative integers
d	Subsystem dimensions

#### Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

# 6.1.4.105 multiidx2n()

```
idx qpp::multiidx2n ( const \ std::vector < \ idx \ > \ \& \ midx, const \ std::vector < \ idx \ > \ \& \ dims \ ) \quad [inline]
```

Multi-index to non-negative integer index.

# See also

```
qpp::n2multiidx()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

#### **Parameters**

m	idx	Multi-index
di	ims	Dimensions of the multi-partite system

# Returns

Non-negative integer index

# 6.1.4.106 n2multiidx()

Non-negative integer index to multi-index.

#### See also

qpp::multiidx2n()

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

# **Parameters**

n	Non-negative integer index
dims	Dimensions of the multi-partite system

#### Returns

Multi-index of the same size as dims

```
6.1.4.107 negativity() [1/2]
```

Negativity of the bi-partite mixed state A.

# **Parameters**

Α	Eigen expression
dims	Dimensions of the bi-partite system

#### Returns

Negativity

# 6.1.4.108 negativity() [2/2]

```
template<typename Derived > double qpp::negativity ( const Eigen::MatrixBase< Derived > & A, idx d = 2)
```

Negativity of the bi-partite mixed state A.

Α	Eigen expression
d	Subsystem dimensions

Negativity

# 6.1.4.109 norm()

Frobenius norm.

#### **Parameters**

```
A Eigen expression
```

#### Returns

Frobenius norm of A

# 6.1.4.110 normalize()

Normalizes state vector (column or row vector) or density matrix.

# Parameters

```
A Eigen expression
```

#### Returns

Normalized state vector or density matrix

# 6.1.4.111 omega()

```
cplx qpp::omega (
        idx D ) [inline]
```

D-th root of unity.

```
D Non-negative integer
```

# Returns

D-th root of unity  $\exp(2\pi i/D)$ 

#### 6.1.4.112 powm()

Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

#### See also

qpp::spectralpowm()

Explicitly multiplies the matrix A with itself n times. By convention  $A^0 = I$ .

#### **Parameters**

Α	Eigen expression
n	Non-negative integer

#### Returns

Matrix power  $A^n$ , as a dynamic matrix over the same scalar field as  ${\it A}$ 

# 6.1.4.113 prj()

# Projector.

Normalized projector onto state vector

# **Parameters**

A Eigen expression

Projector onto the state vector *A*, or the matrix *Zero* if *A* has norm zero, as a dynamic matrix over the same scalar field as *A* 

Element-wise product of A.

#### **Parameters**

```
A Eigen expression
```

#### Returns

Element-wise product of A, as a scalar over the same scalar field as A

Element-wise product of an STL-like range.

# **Parameters**

first	Iterator to the first element of the range
last	Iterator to the last element of the range

#### Returns

Element-wise product of the range, as a scalar over the same scalar field as the range

```
6.1.4.116 prod() [3/3]

template<typename Container >
Container::value_type qpp::prod (
```

```
const Container & c,
typename std::enable_if< is_iterable< Container >::value >::type * = nullptr )
```

Element-wise product of the elements of an STL-like container.

#### **Parameters**

```
c STL-like container
```

#### Returns

Element-wise product of the elements of the container, as a scalar over the same scalar field as the container

Partial trace.

#### See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

#### **Parameters**

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

#### Returns

Partial trace  $Tr_{subsys}(\cdot)$  over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

Partial trace.

#### See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

#### **Parameters**

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

#### Returns

Partial trace  $Tr_{subsys}(\cdot)$  over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

# 6.1.4.119 ptrace1() [1/2]

Partial trace.

#### See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

#### **Parameters**

Α	Eigen expression
dims	Dimensions of the bi-partite system

#### Returns

Partial trace  $Tr_A(\cdot)$  over the first subsytem A in a bi-partite system  $A\otimes B$ , as a dynamic matrix over the same scalar field as A

# 6.1.4.120 ptrace1() [2/2]

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::ptrace1 (
```

```
const Eigen::MatrixBase< Derived > & A, idx d = 2)
```

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

#### **Parameters**

Α	Eigen expression
d	Subsystem dimensions

#### Returns

Partial trace  $Tr_A(\cdot)$  over the first subsytem A in a bi-partite system  $A\otimes B$ , as a dynamic matrix over the same scalar field as A

# 6.1.4.121 ptrace2() [1/2]

Partial trace.

See also

qpp::ptrace1()

Partial trace over the second subsystem of bi-partite state vector or density matrix

#### **Parameters**

Α	Eigen expression
dims	Dimensions of the bi-partite system

# Returns

Partial trace  $Tr_B(\cdot)$  over the second subsytem B in a bi-partite system  $A\otimes B$ , as a dynamic matrix over the same scalar field as A

#### **6.1.4.122** ptrace2() [2/2]

Partial trace.

#### See also

```
qpp::ptrace1()
```

Partial trace over the second subsystem of bi-partite state vector or density matrix

#### **Parameters**

Α	Eigen expression
d	Subsystem dimensions

#### Returns

Partial trace  $Tr_B(\cdot)$  over the second subsystem B in a bi-partite system  $A\otimes B$ , as a dynamic matrix over the same scalar field as A

# 6.1.4.123 ptranspose() [1/2]

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

#### **Parameters**

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

#### Returns

Partial transpose  $(\cdot)^{T_{subsys}}$  over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

#### 6.1.4.124 ptranspose() [2/2]

# Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

#### **Parameters**

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

# Returns

Partial transpose  $(\cdot)^{T_{subsys}}$  over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

#### 6.1.4.125 QFT()

Qudit quantum Fourier transform.

# **Parameters**

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

# Returns

Qudit quantum Fourier transform applied on A

# **6.1.4.126** qmutualinfo() [1/2]

```
template<typename Derived >
double qpp::qmutualinfo (
```

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & subsysA,
const std::vector< idx > & subsysB,
const std::vector< idx > & dims )
```

Quantum mutual information between 2 subsystems of a composite system.

#### **Parameters**

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
dims	Dimensions of the multi-partite system

# Returns

Mutual information between the 2 subsystems

# 6.1.4.127 qmutualinfo() [2/2]

Quantum mutual information between 2 subsystems of a composite system.

#### **Parameters**

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
d	Subsystem dimensions

# Returns

Mutual information between the 2 subsystems

Generates a random real number uniformly distributed in the interval [a, b)

	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

#### Returns

Random real number (double) uniformly distributed in the interval [a, b)

Generates a random big integer uniformly distributed in the interval [a, b].

#### Note

To avoid ambiguity with double qpp::rand(double, double) cast at least one of the arguments to qpp::bigint

#### **Parameters**

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

#### Returns

Random big integer uniformly distributed in the interval [a, b]

Generates a random matrix with entries uniformly distributed in the interval [a, b)

If complex, then both real and imaginary parts are uniformly distributed in [a, b)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED\_TYPE. It is specialized only for qpp::dmat and qpp::cmat

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

#### Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries uniformly distributed in [-1,1)
dmat mat = rand<dmat>(3, 3, -1, 1);
```

#### **Parameters**

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

#### Returns

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

#### Example

```
// generates a 3 x 3 random Eigen::MatrixXcd,
// with entries (both real and imaginary) uniformly distributed in [-1,1)
cmat mat = rand<cmat>(3, 3, -1, 1);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
Geperated	bদ্ৰাপ্তাৰণীhe interval, does not belong to it

Random complex matrix

# 6.1.4.133 randH()

```
cmat qpp::randH (
    idx D = 2 ) [inline]
```

Generates a random Hermitian matrix.

# **Parameters**

D Dimension of the Hilbert space

#### Returns

Random Hermitian matrix

# 6.1.4.134 randidx()

```
idx qpp::randidx (
        idx a = std::numeric_limits<idx>::min(),
        idx b = std::numeric_limits<idx>::max() ) [inline]
```

Generates a random index (idx) uniformly distributed in the interval [a, b].

#### **Parameters**

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

#### Returns

Random index (idx) uniformly distributed in the interval [a, b]

# 6.1.4.135 randket()

```
ket qpp::randket (
    idx D = 2 ) [inline]
```

Generates a random normalized ket (pure state vector)

D Dimension of the Hilbert space

#### Returns

Random normalized ket

#### 6.1.4.136 randkraus()

```
std::vector<cmat> qpp::randkraus (
    idx N,
    idx D = 2) [inline]
```

Generates a set of random Kraus operators.

#### Note

The set of Kraus operators satisfy the closure condition  $\sum_i K_i^\dagger K_i = I$ 

#### **Parameters**

Ν	Number of Kraus operators
D	Dimension of the Hilbert space

# Returns

**6.1.4.137** randn() [1/4]

Set of N Kraus operators satisfying the closure condition

```
template<typename Derived >
Derived qpp::randn (
    idx rows QPP_UNUSED_,
```

idx cols QPP\_UNUSED\_,

double mean QPP\_UNUSED\_ = 0,
double sigma QPP\_UNUSED\_ = 1 )

Generates a random matrix with entries normally distributed in N(mean, sigma)

If complex, then both real and imaginary parts are normally distributed in N(mean, sigma)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED\_TYPE. It is specialized only for qpp::dmat and qpp::cmat

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

#### Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries normally distributed in N(0,2)
dmat mat = randn<dmat>(3, 3, 0, 2);
```

#### **Parameters**

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

#### Returns

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

#### Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd,
// with entries (both real and imaginary) normally distributed in N(0,2)
cmat mat = randn<cmat>(3, 3, 0, 2);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Random complex matrix

Generates a random real number (double) normally distributed in N(mean, sigma)

#### **Parameters**

mean	Mean
sigma	Standard deviation

# Returns

Random real number normally distributed in N(mean, sigma)

# 6.1.4.141 randperm()

```
std::vector<idx> qpp::randperm (
    idx N ) [inline]
```

Generates a random uniformly distributed permutation.

Uses Knuth shuffle method (as implemented by std::shuffle), so that all permutations are equally probable

# **Parameters**

```
N Size of the permutation
```

#### Returns

Random permutation of size N

# 6.1.4.142 randprime()

```
bigint b,
idx N = 1000) [inline]
```

Generates a random big prime uniformly distributed in the interval [a, b].

а	Beginning of the interval, belongs to it	
b	End of the interval, belongs to it	
Ν	Maximum number of candidates	

#### Returns

Random big integer uniformly distributed in the interval [a, b]

# 6.1.4.143 randprob()

```
std::vector<double> qpp::randprob (
    idx N ) [inline]
```

Generates a random probability vector uniformly distributed over the probability simplex.

#### **Parameters**

N Size of the probability vector

#### Returns

Random probability vector

# 6.1.4.144 randrho()

```
cmat qpp::randrho (
    idx D = 2) [inline]
```

Generates a random density matrix.

# **Parameters**

D Dimension of the Hilbert space

# Returns

Random density matrix

# 6.1.4.145 randU()

```
cmat qpp::randU (
    idx D = 2 ) [inline]
```

Generates a random unitary matrix.

# **Parameters**

```
D Dimension of the Hilbert space
```

# Returns

Random unitary

# 6.1.4.146 randV()

Generates a random isometry matrix.

#### **Parameters**

Din	Size of the input Hilbert space
Dout	Size of the output Hilbert space

# Returns

Random isometry matrix

Renyi-  $\alpha$  entropy of the density matrix  ${\it A}$ , for  $\alpha \geq 0$ .

# Note

When lpha o 1 the Renyi entropy converges to the von-Neumann entropy, with the logarithm in base 2

Α	Eigen expression
alpha Non-negative real number, use qpp::infty for $\alpha = \infty$	

#### Returns

Renyi-  $\alpha$  entropy, with the logarithm in base 2

Renyi-  $\alpha$  entropy of the probability distribution *prob*, for  $\alpha \geq 0$ .

#### Note

When  $\alpha \to 1$  the Renyi entropy converges to the Shannon entropy, with the logarithm in base 2

#### **Parameters**

prob	Real probability vector
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

# Returns

Renyi-  $\alpha$  entropy, with the logarithm in base 2

# 6.1.4.149 reshape()

# Reshape.

Uses column-major order when reshaping (same as MATLAB)

Α	Eigen expression
	Number of rows of the reshaped matrix
Genera CO/S	by Poxygen of columns of the reshaped matrix

Reshaped matrix with rows rows and cols columns, as a dynamic matrix over the same scalar field as A

#### 6.1.4.150 rho2bloch()

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

#### See also

qpp::bloch2rho()

#### Note

It is implicitly assumed that the density matrix is Hermitian

#### **Parameters**

A Eigen expression

# Returns

3-dimensional Bloch vector

# 6.1.4.151 rho2pure()

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

#### Note

No purity check is done, the input state A must have rank one, otherwise the function returns the first non-zero eigenvector of A

#### **Parameters**

A Eigen expression, assumed to be proportional to a projector onto a pure state, i.e. A is assumed to have rank one

The unique non-zero eigenvector of A (up to a phase), as a dynamic column vector over the same scalar field as A

#### 6.1.4.152 save()

Saves Eigen expression to a binary file (internal format) in double precision.

#### See also

qpp::load()

#### **Parameters**

Α	Eigen expression
fname	Output file name

# **6.1.4.153** saveMATLAB() [1/2]

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

# See also

qpp::loadMATLAB()

# **Template Parameters**

Complex	Eigen type
Complex	goypo

Α	Eigen expression over the complex field
---	---

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be saved
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details

# **6.1.4.154** saveMATLAB() [2/2]

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

#### See also

qpp::loadMATLAB()

# **Template Parameters**

igen type

#### **Parameters**

Α	Non-complex Eigen expression
mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be saved
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details

# 6.1.4.155 schatten()

# Schatten matrix norm.

Α	Eigen expression
р	Real number, greater or equal to 1, use qpp::infty for $p=\infty$

Schatten-p matrix norm of A

Schmidt basis on Alice side.

#### **Parameters**

Α	Eigen expression
dims	Dimensions of the bi-partite system

# Returns

Unitary matrix  ${\cal U}$  whose columns represent the Schmidt basis vectors on Alice side.

# 

Schmidt basis on Alice side.

#### **Parameters**

Α	Eigen expression
d	Subsystem dimensions

#### Returns

Unitary matrix U whose columns represent the Schmidt basis vectors on Alice side.

# 6.1.4.158 schmidtB() [1/2] template<typename Derived > cmat qpp::schmidtB (

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & dims )
```

Schmidt basis on Bob side.

#### **Parameters**

Α	Eigen expression
dims	Dimensions of the bi-partite system

#### Returns

Unitary matrix  ${\cal V}$  whose columns represent the Schmidt basis vectors on Bob side.

# 

Schmidt basis on Bob side.

idx d = 2)

#### **Parameters**

Α	Eigen expression
d	Subsystem dimensions

# Returns

Unitary matrix  ${\cal V}$  whose columns represent the Schmidt basis vectors on Bob side.

# 

Schmidt coefficients of the bi-partite pure state A.

# Note

The sum of the squares of the Schmidt coefficients equals 1

# See also

qpp::schmidtprobs()

Α	Eigen expression
dims	Dimensions of the bi-partite system

#### Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

# **6.1.4.161** schmidtcoeffs() [2/2]

Schmidt coefficients of the bi-partite pure state A.

#### Note

The sum of the squares of the Schmidt coefficients equals 1

#### See also

qpp::schmidtprobs()

#### **Parameters**

Α	Eigen expression
d	Subsystem dimensions

# Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

# **6.1.4.162** schmidtprobs() [1/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

#### See also

qpp::schmidtcoeffs()

#### **Parameters**

Α	Eigen expression
dims	Dimensions of the bi-partite system

#### Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

# 6.1.4.163 schmidtprobs() [2/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

# See also

qpp::schmidtcoeffs()

# **Parameters**

Α	Eigen expression
d	Subsystem dimensions

# Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

#### 6.1.4.164 sigma()

#### Standard deviation.

prob	Real probability vector representing the probability distribution of $X$
X	Real random variable values represented by an STL-like container

#### Returns

Standard deviation of X

# 6.1.4.165 sinm()

Matrix sin.

#### **Parameters**

A Eigen expression

#### Returns

Matrix sine of A

# 6.1.4.166 spectralpowm()

Matrix power.

# See also

qpp::powm()

Uses the spectral decomposition of  $\emph{A}$  to compute the matrix power. By convention  $\emph{A}^0 = \emph{I}$  .

Α	Eigen expression
Z	Complex number

Matrix power  $A^z$ 

# 6.1.4.167 sqrtm()

Matrix square root.

#### **Parameters**

```
A Eigen expression
```

#### Returns

Matrix square root of A

```
6.1.4.168 sum() [1/3]
```

Element-wise sum of A.

#### **Parameters**

```
A Eigen expression
```

# Returns

Element-wise sum of A, as a scalar over the same scalar field as A

```
6.1.4.169 sum() [2/3]
```

Element-wise sum of an STL-like range.

first	Iterator to the first element of the range
last	Iterator to the last element of the range

#### Returns

Element-wise sum of the range, as a scalar over the same scalar field as the range

Element-wise sum of the elements of an STL-like container.

#### **Parameters**

```
c STL-like container
```

#### Returns

Element-wise sum of the elements of the container, as a scalar over the same scalar field as the container

# 6.1.4.171 super2choi()

Converts superoperator matrix to Choi matrix.

# See also

qpp::choi2super()

#### **Parameters**

A Superoperator matrix

Choi matrix

# 6.1.4.172 svals()

Singular values.

#### **Parameters**

A Eigen expression

#### Returns

Singular values of A, ordered in decreasing order, as a real dynamic column vector

#### 6.1.4.173 svd()

Full singular value decomposition.

#### **Parameters**

A Eigen expression

# Returns

Tuple of: 1. Left sigular vectors of A, as columns of a complex dynamic matrix, 2. Singular values of A, ordered in decreasing order, as a real dynamic column vector, and 3. Right singular vectors of A, as columns of a complex dynamic matrix

# 6.1.4.174 svdU()

Left singular vectors.

```
A Eigen expression
```

# Returns

Complex dynamic matrix, whose columns are the left singular vectors of A

#### 6.1.4.175 svdV()

Right singular vectors.

# **Parameters**

```
A Eigen expression
```

#### Returns

Complex dynamic matrix, whose columns are the right singular vectors of A

# 6.1.4.176 syspermute() [1/2]

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Α	Eigen expression
perm	Permutation
dims	Dimensions of the multi-partite system

Permuted system, as a dynamic matrix over the same scalar field as A

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit *perm[i]* is permuted to the location *i*.

#### **Parameters**

Α	Eigen expression
perm	Permutation
d	Subsystem dimensions

#### Returns

Permuted system, as a dynamic matrix over the same scalar field as A

# 6.1.4.178 TFQ()

Inverse (adjoint) qudit quantum Fourier transform.

# **Parameters**

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

# Returns

Inverse (adjoint) qudit quantum Fourier transform applied on A

#### 6.1.4.179 trace()

Trace.

**Parameters** 

```
A Eigen expression
```

#### Returns

Trace of A, as a scalar over the same scalar field as A

# 6.1.4.180 transpose()

Transpose.

**Parameters** 

```
A Eigen expression
```

Returns

Transpose of A, as a dynamic matrix over the same scalar field as A

```
6.1.4.181 tsallis() [1/2] template<typename Derived > double qpp::tsallis ( const Eigen::MatrixBase< Derived > & A, double q)
```

Tsallis- q entropy of the density matrix A, for  $q \ge 0$ .

Note

When  $q \to 1$  the Tsallis entropy converges to the von-Neumann entropy, with the logarithm in base e

Α	Eigen expression
q	Non-negative real number

#### Returns

Tsallis- q entropy

```
6.1.4.182 tsallis() [2/2] double qpp::tsallis ( const std::vector< double > & prob, double q ) [inline]
```

Tsallis- q entropy of the probability distribution *prob*, for  $q \ge 0$ .

#### Note

When  $q \to 1$  the Tsallis entropy converges to the Shannon entropy, with the logarithm in base e

# **Parameters**

prob	Real probability vector
q	Non-negative real number

# Returns

 ${\sf Tsallis-}\ q\ {\sf entropy}$ 

# 6.1.4.183 uniform()

```
std::vector<double> qpp::uniform (
    idx N ) [inline]
```

Uniform probability distribution vector.

# **Parameters**

N Size of the alphabet

#### Returns

Real vector consisting of a uniform distribution of size N

#### 6.1.4.184 var()

Variance.

#### **Parameters**

prob	Real probability vector representing the probability distribution of $\lambda$	
Χ	Real random variable values represented by an STL-like container	

#### Returns

Variance of X

#### 6.1.4.185 x2contfrac()

Simple continued fraction expansion.

#### See also

```
qpp::contfrac2x()
```

#### **Parameters**

Х	Real number	
Ν	Maximum number of terms in the expansion	
cut	cut Stop the expansion when the next term is greater than cu	

#### Returns

Integer vector containing the simple continued fraction expansion of x. If there are M less than N terms in the expansion, a shorter vector with M components is returned.

## 6.1.5 Variable Documentation

### 6.1.5.1 chop

```
constexpr double qpp::chop = 1e-16
```

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

#### 6.1.5.2 ee

```
constexpr double qpp::ee = 2.718281828459045235360287471352662497
```

Base of natural logarithm, e.

#### 6.1.5.3 infty

```
constexpr double qpp::infty = std::numeric_limits<double>::max()
```

Used to denote infinity in double precision.

## 6.1.5.4 maxn

```
constexpr idx qpp::maxn = 64
```

Maximum number of allowed qubits/qudits (subsystems)

Used internally to allocate arrays on the stack (for performance reasons):

## 6.1.5.5 pi

```
constexpr double qpp::pi = 3.141592653589793238462643383279502884 \pi
```

## 6.2 qpp::exception Namespace Reference

Quantum++ exception hierarchy namespace.

#### Classes

class CustomException

Custom exception.

· class DimsInvalid

Invalid dimension(s) exception.

· class DimsMismatchCvector

Dimension(s) mismatch column vector size exception.

· class DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

· class DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

· class DimsMismatchVector

Dimension(s) mismatch vector size exception.

· class DimsNotEqual

Dimensions not equal exception.

class Duplicates

System (e.g. std::vector) has duplicates exception.

class Exception

Base class for generating Quantum++ custom exceptions.

· class InvalidIterator

Invalid iterator.

class MatrixMismatchSubsys

Matrix mismatch subsystems exception.

class MatrixNotCvector

Matrix is not a column vector exception.

· class MatrixNotRvector

Matrix is not a row vector exception.

class MatrixNotSquare

Matrix is not square exception.

class MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

class MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

class MatrixNotSquareNorVector

Matrix is not square nor vector exception.

class MatrixNotVector

Matrix is not a vector exception.

class NoCodeword

Codeword does not exist exception.

· class NotBipartite

Not bi-partite exception.

class NotImplemented

Code not yet implemented.

class NotQubitCvector

Column vector is not 2 x 1 exception.

class NotQubitMatrix

Matrix is not 2 x 2 exception.

class NotQubitRvector

Row vector is not 1 x 2 exception.

class NotQubitSubsys

Subsystems are not qubits exception.

· class NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

class OutOfRange

Argument out of range exception.

class PermInvalid

Invalid permutation exception.

class PermMismatchDims

Permutation mismatch dimensions exception.

· class QuditAlreadyMeasured

Qudit was already measured exception.

· class SizeMismatch

Size mismatch exception.

· class SubsysMismatchDims

Subsystems mismatch dimensions exception.

class TypeMismatch

Type mismatch exception.

class UndefinedType

Not defined for this type exception.

· class Unknown

Unknown exception.

· class ZeroSize

Object has zero size exception.

## 6.2.1 Detailed Description

Quantum++ exception hierarchy namespace.

## 6.3 qpp::experimental Namespace Reference

Experimental/test functions/classes, do not use or modify.

### 6.3.1 Detailed Description

Experimental/test functions/classes, do not use or modify.

## 6.4 qpp::internal Namespace Reference

Internal utility functions, do not use them directly or modify them.

#### **Classes**

- struct Display\_Impl\_
- class EqualEigen

Functor for comparing Eigen expressions for equality.

class EqualSameSizeStringDits

Functor for comparing strings of numbers of equal sizes in lexicographical order. Establishes a strict weak ordering relation.

· class HashEigen

Functor for hashing Eigen expressions.

- class IOManipEigen
- class IOManipPointer
- · class IOManipRange
- class Singleton

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

#### **Functions**

template < class T > void hash\_combine (std::size\_t &seed, const T &v)

Hash combine.

- void n2multiidx (idx n, idx numdims, const idx \*const dims, idx \*result) noexcept
- idx multiidx2n (const idx \*const midx, idx numdims, const idx \*const dims) noexcept
- $\bullet \ \ {\sf template}{<} {\sf typename \ Derived}>$

bool check\_square\_mat (const Eigen::MatrixBase< Derived > &A)

• template<typename Derived >

bool check\_vector (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$ 

bool <a href="mailto:check\_rvector">bool check\_rvector</a> (const Eigen::MatrixBase</a> Derived > &A)

 $\bullet \ \ \text{template}{<} \text{typename Derived} >$ 

bool <a href="mailto:check\_cvector">check\_cvector</a> (const Eigen::MatrixBase</a> Derived > &A)

• template<typename T >

bool check\_nonzero\_size (const T &x) noexcept

• template<typename T1 , typename T2 >

bool check\_matching\_sizes (const T1 &lhs, const T2 &rhs) noexcept

- bool check\_dims (const std::vector< idx > &dims)
- template<typename Derived >

 $bool\ check\_dims\_match\_mat\ (const\ std::vector < idx > \&dims,\ const\ Eigen::MatrixBase < Derived > \&A)$ 

• template<typename Derived >

bool check\_dims\_match\_cvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

• template<typename Derived >

bool check\_dims\_match\_rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- bool check eq dims (const std::vector< idx > &dims, idx dim) noexcept
- bool check no duplicates (std::vector < idx > v)
- bool check\_subsys\_match\_dims (const std::vector < idx > &subsys, const std::vector < idx > &dims)
- template<typename Derived >

bool check\_qubit\_matrix (const Eigen::MatrixBase< Derived > &A) noexcept

• template<typename Derived >

 $bool\ check\_qubit\_cvector\ (const\ Eigen::MatrixBase < Derived > \&A)\ no except$ 

• template<typename Derived >

bool check qubit rvector (const Eigen::MatrixBase< Derived > &A) noexcept

• template<typename Derived >

bool check\_qubit\_vector (const Eigen::MatrixBase< Derived > &A) noexcept

- bool check\_perm (const std::vector< idx > &perm)
- template<typename Derived1, typename Derived2 >
   dyn\_mat< typename Derived1::Scalar > kron2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::
   MatrixBase< Derived2 > &B)
- template<typename Derived1, typename Derived2 >
   dyn\_mat< typename Derived1::Scalar > dirsum2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen
   ::MatrixBase< Derived2 > &B)
- template<typename T >
   void variadic\_vector\_emplace (std::vector< T > &)
- template<typename T, typename First, typename... Args>
   void variadic\_vector\_emplace (std::vector< T > &v, First &&first, Args &&... args)
- idx get\_num\_subsys (idx D, idx d)
- idx get\_dim\_subsys (idx sz, idx N)
- template<typename T, typename std::enable\_if< std::numeric\_limits< T >::is\_iec559||is\_complex< T >::value >::type \* = nullptr>
   T abs\_chop (const T &x, double chop=qpp::chop)
- template<typename T, typename std::enable\_if<!(std::numeric\_limits< T >::is\_iec559||is\_complex< T >::value)>::type \* = nullptr> T abs\_chop (const T &x, double QPP\_UNUSED\_chop=qpp::chop)

#### 6.4.1 Detailed Description

Internal utility functions, do not use them directly or modify them.

#### 6.4.2 Function Documentation

```
6.4.2.1 abs_chop() [1/2]
```

#### 6.4.2.2 abs\_chop() [2/2]

```
6.4.2.3 check_cvector()
```

```
template<typename Derived >
bool qpp::internal::check_cvector (
             const Eigen::MatrixBase< Derived > & A )
6.4.2.4 check_dims()
bool qpp::internal::check_dims (
             const std::vector< idx > & dims ) [inline]
6.4.2.5 check_dims_match_cvect()
{\tt template}{<}{\tt typename \ Derived} \,>\,
bool qpp::internal::check\_dims\_match\_cvect (
             const std::vector< idx > & dims,
             const Eigen::MatrixBase< Derived > & A )
6.4.2.6 check_dims_match_mat()
template<typename Derived >
bool qpp::internal::check_dims_match_mat (
             const std::vector< idx > & dims,
             const Eigen::MatrixBase< Derived > & A )
6.4.2.7 check_dims_match_rvect()
template<typename Derived >
bool qpp::internal::check_dims_match_rvect (
             const std::vector< idx > & dims,
             const Eigen::MatrixBase< Derived > & A )
6.4.2.8 check_eq_dims()
bool qpp::internal::check_eq_dims (
             const std::vector< idx > & dims,
             idx dim ) [inline], [noexcept]
```

#### 6.4.2.9 check\_matching\_sizes()

```
template<typename T1 , typename T2 >
bool qpp::internal::check_matching_sizes (
            const T1 & lhs,
             const T2 & rhs ) [noexcept]
6.4.2.10 check_no_duplicates()
bool qpp::internal::check_no_duplicates (
            std::vector < idx > v) [inline]
6.4.2.11 check_nonzero_size()
template<typename T >
bool qpp::internal::check_nonzero_size (
            const T & x ) [noexcept]
6.4.2.12 check_perm()
bool qpp::internal::check_perm (
            const std::vector< idx > & perm ) [inline]
6.4.2.13 check_qubit_cvector()
template<typename Derived >
bool qpp::internal::check_qubit_cvector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.14 check_qubit_matrix()
template<typename Derived >
bool qpp::internal::check_qubit_matrix (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
```

```
6.4.2.15 check_qubit_rvector()
```

```
template<typename Derived >
bool qpp::internal::check_qubit_rvector (
             const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.16 check_qubit_vector()
template<typename Derived >
bool qpp::internal::check_qubit_vector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.17 check_rvector()
template<typename Derived >
bool qpp::internal::check_rvector (
             const Eigen::MatrixBase< Derived > & A )
6.4.2.18 check_square_mat()
template < typename Derived >
bool qpp::internal::check_square_mat (
             const Eigen::MatrixBase< Derived > & A )
6.4.2.19 check_subsys_match_dims()
bool qpp::internal::check_subsys_match_dims (
            const std::vector< idx > & subsys,
             const std::vector< idx > & dims ) [inline]
6.4.2.20 check_vector()
template < typename Derived >
bool qpp::internal::check_vector (
            const Eigen::MatrixBase< Derived > & A )
```

#### 6.4.2.21 dirsum2()

#### 6.4.2.22 get\_dim\_subsys()

#### 6.4.2.23 get\_num\_subsys()

#### 6.4.2.24 hash\_combine()

Hash combine.

## **Template Parameters**

|--|

#### **Parameters**

seed	Initial seed, will be updated by the function
V	Value with which the hash is combined

#### 6.4.2.25 kron2()

```
template<typename Derived1 , typename Derived2 >
dyn_mat<typename Derived1::Scalar> qpp::internal::kron2 (
```

```
const Eigen::MatrixBase< Derived1 > & A,
const Eigen::MatrixBase< Derived2 > & B )
```

## 6.4.2.26 multiidx2n()

### 6.4.2.27 n2multiidx()

#### 6.4.2.28 variadic\_vector\_emplace() [1/2]

```
template<typename T > void qpp::internal::variadic_vector_emplace ( std::vector < T \ > \& \ )
```

#### 6.4.2.29 variadic\_vector\_emplace() [2/2]

## 6.5 qpp::literals Namespace Reference

## **Functions**

```
• constexpr cplx operator""_i (unsigned long long int x) noexcept
      User-defined literal for complex i = \sqrt{-1} (integer overload)

    constexpr cplx operator""_i (long double x) noexcept

      User-defined literal for complex i = \sqrt{-1} (real overload)
• constexpr std::complex< float > operator""_if (unsigned long long int x) noexcept
      User-defined literal for complex i = \sqrt{-1} (integer overload)
• constexpr std::complex< float > operator""_if (long double x) noexcept
      User-defined literal for complex i = \sqrt{-1} (real overload)
• template<char... Bits>
  ket operator""_ket ()
      Multi-partite qubit ket user-defined literal.
• template<char... Bits>
  bra operator""_bra ()
      Multi-partite qubit bra user-defined literal.
• template<char... Bits>
  cmat operator""_prj ()
      Multi-partite qubit projector user-defined literal.
```

#### 6.5.1 Function Documentation

```
6.5.1.1 operator"""_bra()

template<char... Bits>
bra qpp::literals::operator""_bra ( )
```

Multi-partite qubit bra user-defined literal.

#### See also

```
qpp::mket() and qpp::adjoint()
```

Constructs the multi-partite qubit bra  $\langle Bits |$ 

**Template Parameters** 

Bits String of binary numbers representing the qubit bra

#### Returns

Multi-partite qubit bra, as a complex dynamic row vector

```
6.5.1.2 operator"""_i() [1/2]
constexpr cplx qpp::literals::operator""_i (
              unsigned long long int x ) [inline], [noexcept]
User-defined literal for complex i = \sqrt{-1} (integer overload)
Example:
cplx z = 4_i; // type of z is std::complex<double>
6.5.1.3 operator"""_i() [2/2]
constexpr cplx qpp::literals::operator""_i (
              long double x ) [inline], [noexcept]
User-defined literal for complex i = \sqrt{-1} (real overload)
Example:
cplx z = 4.5_i; // type of z is std::complex<double>
6.5.1.4 operator"""_if() [1/2]
constexpr std::complex<float> qpp::literals::operator""_if (
              unsigned long long int x ) [inline], [noexcept]
User-defined literal for complex i = \sqrt{-1} (integer overload)
Example:
auto \dot{z} = 4_if; // type of z is std::complex<double>
6.5.1.5 operator"""_if() [2/2]
constexpr std::complex<float> qpp::literals::operator""_if (
              long double x ) [inline], [noexcept]
User-defined literal for complex i = \sqrt{-1} (real overload)
Example:
auto z = 4.5_if; // type of z is std::complex<float>
6.5.1.6 operator"""_ket()
template<char... Bits>
ket qpp::literals::operator""_ket ( )
Multi-partite qubit ket user-defined literal.
See also
     qpp::mket()
```

Constructs the multi-partite qubit ket  $|Bits\rangle$ 

## **Template Parameters**

Bits	String of binary numbers representing the qubit ket	
------	---	--

#### Returns

Multi-partite qubit ket, as a complex dynamic column vector

## 6.5.1.7 operator"""\_prj()

```
template<char... Bits>
cmat qpp::literals::operator""_prj ( )
```

Multi-partite qubit projector user-defined literal.

#### See also

qpp::mprj()

Constructs the multi-partite qubit projector  $|Bits\rangle\langle Bits|$  (in the computational basis)

## **Template Parameters**

Bits String of binary numbers representing the qubit state to project on

## Returns

Multi-partite qubit projector, as a complex dynamic matrix

# **Chapter 7**

# **Class Documentation**

## 7.1 qpp::Bit\_circuit Class Reference


Classical reversible circuit simulator.

#include <classes/reversible.h>

Inheritance diagram for qpp::Bit\_circuit:



Collaboration diagram for qpp::Bit\_circuit:



## **Public Member Functions**

• Bit\_circuit (idx n)

Constructs a bit circuit instance.

• Bit\_circuit (const Dynamic\_bitset &dynamic\_bitset)

Conversion constructor, used to initialize a qpp::Bit\_circuit with a qpp::Dynamic\_bitset.

Bit\_circuit & X (idx i)

Bit flip.

• virtual  $\sim$ Bit\_circuit ()=default

Default virtual destructor.

• Bit\_circuit & NOT (idx i)

Bit flip.

• Bit\_circuit & CNOT (idx ctrl, idx target)

Controlled-NOT.

• Bit\_circuit & TOF (idx i, idx j, idx k)

Toffoli gate.

• Bit\_circuit & SWAP (idx i, idx j)

Swap bits.

• Bit\_circuit & FRED (idx i, idx j, idx k)

Fredkin gate (Controlled-SWAP)

Bit\_circuit & reset () noexcept

Reset the circuit all zero, clear all gates.

- idx get\_gate\_count (const std::string &name={}) const Bit circuit gate count.
- idx get\_gate\_depth (const std::string &name={}) const Bit circuit gate depth.

#### **Private Attributes**

- std::unordered\_map< std::string, idx > depth\_ {}
   gate depths
- Dynamic\_bitset bNOT\_
- Dynamic\_bitset bCNOT\_
- Dynamic\_bitset bSWAP\_
- Dynamic\_bitset bTOF\_
- Dynamic\_bitset bFRED\_
- Dynamic\_bitset btotal\_

used for depth calculations

## **Additional Inherited Members**

## 7.1.1 Detailed Description

Classical reversible circuit simulator.

#### 7.1.2 Constructor & Destructor Documentation

```
7.1.2.1 Bit_circuit() [1/2]

qpp::Bit_circuit::Bit_circuit (
        idx n ) [inline], [explicit]
```

Constructs a bit circuit instance.

#### **Parameters**

n Number of classical bits

Conversion constructor, used to initialize a qpp::Bit\_circuit with a qpp::Dynamic\_bitset.

#### **Parameters**

```
dynamic_bitset Dynamic bitset
```

```
7.1.2.3 ∼Bit_circuit()
```

```
virtual qpp::Bit_circuit::~Bit_circuit ( ) [virtual], [default]
```

Default virtual destructor.

## 7.1.3 Member Function Documentation

## 7.1.3.1 CNOT()

Controlled-NOT.

## **Parameters**

ctrl	Control bit index
target	Target bit index

#### Returns

Reference to the current instance

## 7.1.3.2 FRED()

```
Bit_circuit& qpp::Bit_circuit::FRED (
    idx i,
    idx j,
    idx k) [inline]
```

Fredkin gate (Controlled-SWAP)

#### **Parameters**

i	Control bit index	
j	Target first bit index	
k	k Target second bit index	

#### Returns

Reference to the current instance

#### 7.1.3.3 get\_gate\_count()

Bit circuit gate count.

Note

If name is empty (default), returns the total gate count of the circuit

#### **Parameters**

## Returns

Gate count

#### 7.1.3.4 get\_gate\_depth()

Bit circuit gate depth.

Note

If name is empty (default), returns the total gate depth of the circuit

#### **Parameters**

name	Gate name (option	nal). Possible names are N	NOT (X), CNOT, SWAP, TOF, FRED.

```
Returns
```

Gate depth

```
7.1.3.5 NOT()
```

```
Bit_circuit& qpp::Bit_circuit::NOT (
        idx i ) [inline]
```

Bit flip.

See also

```
qpp::Bit_circuit::X()
```

#### **Parameters**

```
i Bit position in the circuit
```

#### Returns

Reference to the current instance

```
7.1.3.6 reset()
```

```
Bit_circuit& qpp::Bit_circuit::reset ( ) [inline], [noexcept]
```

Reset the circuit all zero, clear all gates.

### Returns

Reference to the current instance

## 7.1.3.7 SWAP()

```
Bit_circuit& qpp::Bit_circuit::SWAP (
         idx i,
         idx j) [inline]
```

Swap bits.

## **Parameters**

i	Bit index
j	Bit index

## Returns

Reference to the current instance

## 7.1.3.8 TOF()

```
Bit_circuit& qpp::Bit_circuit::TOF (
    idx i,
    idx j,
    idx k) [inline]
```

Toffoli gate.

### **Parameters**

i	Control first bit index
j	Control second bit index
k	Target bit index

#### Returns

Reference to the current instance

## 7.1.3.9 X()

```
Bit_circuit& qpp::Bit_circuit::X (
        idx i) [inline]
```

Bit flip.

See also

```
qpp::Bit_circuit::NOT()
```

#### **Parameters**

i Bit position in the circuit

#### Returns

Reference to the current instance

## 7.1.4 Member Data Documentation

```
7.1.4.1 bCNOT_
Dynamic_bitset qpp::Bit_circuit::bCNOT_ [private]
7.1.4.2 bFRED_
Dynamic_bitset qpp::Bit_circuit::bFRED_ [private]
7.1.4.3 bNOT_
Dynamic_bitset qpp::Bit_circuit::bNOT_ [private]
7.1.4.4 bSWAP_
Dynamic_bitset qpp::Bit_circuit::bSWAP_ [private]
7.1.4.5 bTOF_
Dynamic_bitset qpp::Bit_circuit::bTOF_ [private]
7.1.4.6 btotal_
Dynamic_bitset qpp::Bit_circuit::btotal_ [private]
used for depth calculations
```

```
7.1.4.7 count_
```

```
std::unordered_map<std::string, idx> qpp::Bit_circuit::count_ {} [private]
gate counts
```

#### 7.1.4.8 depth\_

```
std::unordered_map<std::string, idx> qpp::Bit_circuit::depth_ {} [private]
gate depths
```

The documentation for this class was generated from the following file:


· classes/reversible.h

## 7.2 qpp::Codes Class Reference


const Singleton class that defines quantum error correcting codes

```
#include <classes/codes.h>
```

Inheritance diagram for qpp::Codes:



Collaboration diagram for qpp::Codes:



## **Public Types**

enum Type { Type::FIVE\_QUBIT, Type::SEVEN\_QUBIT\_STEANE, Type::NINE\_QUBIT\_SHOR }
 Code types, add more codes here if needed.

## **Public Member Functions**

ket codeword (Type type, idx i) const
 Returns the codeword of the specified code type.

## **Private Member Functions**

• Codes ()

Default constructor.

∼Codes ()=default

Default destructor.

#### **Friends**

class internal::Singleton < const Codes >

## **Additional Inherited Members**

### 7.2.1 Detailed Description

const Singleton class that defines quantum error correcting codes

## 7.2.2 Member Enumeration Documentation

### 7.2.2.1 Type

```
enum qpp::Codes::Type [strong]
```

Code types, add more codes here if needed.

## See also

qpp::Codes::codeword()

#### **Enumerator**

FIVE_QUBIT	[[5,1,3]] qubit code
SEVEN_QUBIT_STEANE	[[7,1,3]] Steane qubit code
NINE_QUBIT_SHOR	[[9,1,3]] Shor qubit code

## 7.2.3 Constructor & Destructor Documentation

## 7.2.3.1 Codes()

```
qpp::Codes::Codes ( ) [inline], [private]
```

Default constructor.

#### 7.2.3.2 ∼Codes()

```
qpp::Codes::~Codes ( ) [private], [default]
```

Default destructor.

## 7.2.4 Member Function Documentation

## 7.2.4.1 codeword()

Returns the codeword of the specified code type.

#### See also

```
qpp::Codes::Type
```

#### **Parameters**

type	Code type
i	Codeword index

## Returns

i-th codeword of the code type

## 7.2.5 Friends And Related Function Documentation

7.2.5.1 internal::Singleton < const Codes >

```
friend class internal::Singleton< const Codes > [friend]
```

The documentation for this class was generated from the following file:


· classes/codes.h

## 7.3 qpp::exception::CustomException Class Reference


Custom exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::CustomException:



Collaboration diagram for qpp::exception::CustomException:



## **Public Member Functions**

• CustomException (const std::string &where, const std::string &what)

### **Private Member Functions**

• std::string description () const override Exception description.

#### **Private Attributes**

std::string what\_{{}}

## 7.3.1 Detailed Description

Custom exception.

Custom exception, the user must provide a custom message

#### 7.3.2 Constructor & Destructor Documentation

#### 7.3.2.1 CustomException()

#### 7.3.3 Member Function Documentation

#### 7.3.3.1 description()

```
std::string qpp::exception::CustomException::description ( ) const [inline], [override],
[private], [virtual]
```

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

#### 7.3.4 Member Data Documentation

#### 7.3.4.1 what\_

```
std::string qpp::exception::CustomException::what_ {} [private]
```

The documentation for this class was generated from the following file:


· classes/exception.h

## 7.4 qpp::exception::DimsInvalid Class Reference

Invalid dimension(s) exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsInvalid:



Collaboration diagram for qpp::exception::DimsInvalid:



## **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

## 7.4.1 Detailed Description

Invalid dimension(s) exception.

std::vector<idx> of dimensions has zero size or contains zeros

#### 7.4.2 Member Function Documentation

## 7.4.2.1 description()

std::string qpp::exception::DimsInvalid::description ( ) const [inline], [override], [virtual]

Exception description.

### Returns

**Exception** description

Implements qpp::exception::Exception.

#### 7.4.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

where Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

## 7.5 qpp::exception::DimsMismatchCvector Class Reference


Dimension(s) mismatch column vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchCvector:



Collaboration diagram for qpp::exception::DimsMismatchCvector:



#### **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

## 7.5.1 Detailed Description

Dimension(s) mismatch column vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a column vector)

#### 7.5.2 Member Function Documentation

#### 7.5.2.1 description()

std::string qpp::exception::DimsMismatchCvector::description ( ) const [inline], [override],
[virtual]

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

### 7.5.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

## 7.6 qpp::exception::DimsMismatchMatrix Class Reference


Dimension(s) mismatch matrix size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchMatrix:



Collaboration diagram for qpp::exception::DimsMismatchMatrix:



## **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

## 7.6.1 Detailed Description

Dimension(s) mismatch matrix size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of rows of the Eigen::Matrix (assumed to be a square matrix)

#### 7.6.2 Member Function Documentation

#### 7.6.2.1 description()

```
std::string qpp::exception::DimsMismatchMatrix::description ( ) const [inline], [override],
[virtual]
```

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

### 7.6.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:

classes/exception.h

## 7.7 qpp::exception::DimsMismatchRvector Class Reference


Dimension(s) mismatch row vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchRvector:



Collaboration diagram for qpp::exception::DimsMismatchRvector:



#### **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

## 7.7.1 Detailed Description

Dimension(s) mismatch row vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row vector)

#### 7.7.2 Member Function Documentation

#### 7.7.2.1 description()

std::string qpp::exception::DimsMismatchRvector::description ( ) const [inline], [override],
[virtual]

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

### 7.7.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.8 qpp::exception::DimsMismatchVector Class Reference


Dimension(s) mismatch vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchVector:



Collaboration diagram for qpp::exception::DimsMismatchVector:



# **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

# 7.8.1 Detailed Description

Dimension(s) mismatch vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row/column vector)

#### 7.8.2 Member Function Documentation

#### 7.8.2.1 description()

std::string qpp::exception::DimsMismatchVector::description ( ) const [inline], [override],
[virtual]

Exception description.

## Returns

**Exception** description

Implements qpp::exception::Exception.

# 7.8.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


classes/exception.h

# 7.9 qpp::exception::DimsNotEqual Class Reference


Dimensions not equal exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsNotEqual:



Collaboration diagram for qpp::exception::DimsNotEqual:



# **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

# 7.9.1 Detailed Description

Dimensions not equal exception.

Local/global dimensions are not equal

## 7.9.2 Member Function Documentation

## 7.9.2.1 description()

std::string qpp::exception::DimsNotEqual::description ( ) const [inline], [override], [virtual]

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

## 7.9.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:

· classes/exception.h

# 7.10 qpp::internal::Display\_Impl\_ Struct Reference

```
#include <internal/util.h>
```

Inheritance diagram for qpp::internal::Display\_Impl\_:



#### **Public Member Functions**

template<typename T >
 std::ostream & display\_impl\_ (const T &A, std::ostream &os, double chop=qpp::chop) const

# 7.10.1 Member Function Documentation

# 7.10.1.1 display\_impl\_()

The documentation for this struct was generated from the following file:


• internal/util.h

# 7.11 qpp::exception::Duplicates Class Reference


System (e.g. std::vector) has duplicates exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Duplicates:



Collaboration diagram for qpp::exception::Duplicates:



## **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

# 7.11.1 Detailed Description

System (e.g. std::vector) has duplicates exception.

#### 7.11.2 Member Function Documentation

## 7.11.2.1 description()

```
std::string qpp::exception::Duplicates::description ( ) const [inline], [override], [virtual]
```

Exception description.

## Returns

**Exception** description

Implements qpp::exception::Exception.

# 7.11.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.12 qpp::Dynamic\_bitset Class Reference


Dynamic bitset class, allows the specification of the number of bits at runtime.

#include <classes/reversible.h>

Inheritance diagram for qpp::Dynamic\_bitset:



Collaboration diagram for qpp::Dynamic\_bitset:



# **Public Types**

- using value\_type = unsigned int type of the storage elements
- using storage\_type = std::vector< value\_type > type of the storage

# **Public Member Functions**

• Dynamic\_bitset (idx n)

Constructor, initializes all bits to false (zero)

virtual ~Dynamic\_bitset ()=default

Default virtual destructor.

const storage\_type & data () const

Raw storage space of the bitset.

idx size () const noexcept

Number of bits stored in the bitset.

• idx storage\_size () const noexcept

Size of the underlying storage space (in units of value\_type, unsigned int by default)

· idx count () const noexcept

Number of bits set to one in the bitset (Hamming weight)

· bool get (idx pos) const noexcept

The value of the bit at position pos.

• bool none () const noexcept

Checks whether none of the bits are set.

• bool all () const noexcept

Checks whether all bits are set.

· bool any () const noexcept

Checks whether any bit is set.

Dynamic\_bitset & set (idx pos, bool value=true)

Sets the bit at position pos.

• Dynamic\_bitset & set () noexcept

Set all bits to true.

Dynamic\_bitset & rand (idx pos, double p=0.5)

Sets the bit at position pos according to a Bernoulli(p) distribution.

Dynamic\_bitset & rand (double p=0.5)

Sets all bits according to a Bernoulli(p) distribution.

• Dynamic\_bitset & reset (idx pos)

Sets the bit at position pos to false.

• Dynamic\_bitset & reset () noexcept

Sets all bits to false.

• Dynamic\_bitset & flip (idx pos)

Flips the bit at position pos.

• Dynamic\_bitset & flip () noexcept

Flips all bits.

bool operator== (const Dynamic\_bitset &rhs) const noexcept

Equality operator.

bool operator!= (const Dynamic\_bitset &rhs) const noexcept

Inequality operator.

idx operator- (const Dynamic\_bitset &rhs) const noexcept

Number of places the two bitsets differ (Hamming distance)

template < class CharT = char, class Traits = std::char\_traits < CharT>, class Allocator = std::allocator < CharT>> std::basic\_string < CharT, Traits, Allocator > to\_string (CharT zero=CharT('0'), CharT one=CharT('1')) const String representation.

# **Protected Member Functions**

• idx index\_ (idx pos) const

Index of the pos bit in the storage space.

idx offset\_ (idx pos) const

Offset of the pos bit in the storage space relative to its index.

## **Protected Attributes**

```
    idx storage_size_
        storage size
    idx n_
        number of bits
    std::vector < value_type > v_
        storage space
```

## **Private Member Functions**

## 7.12.1 Detailed Description

Dynamic bitset class, allows the specification of the number of bits at runtime.

Note

The interface mimics std::bitset<>

# 7.12.2 Member Typedef Documentation

```
7.12.2.1 storage_type
using qpp::Dynamic_bitset::storage_type = std::vector<value_type>
type of the storage

7.12.2.2 value_type
using qpp::Dynamic_bitset::value_type = unsigned int
type of the storage elements
```

# 7.12.3 Constructor & Destructor Documentation

```
7.12.3.1 Dynamic_bitset()
```

```
qpp::Dynamic_bitset ::Dynamic_bitset (
          idx n ) [inline], [explicit]
```

Constructor, initializes all bits to false (zero)

```
Parameters
```

*n* Number of bits in the bitset

```
7.12.3.2 ~Dynamic_bitset()
```

```
virtual qpp::Dynamic_bitset::~Dynamic_bitset ( ) [virtual], [default]
```

Default virtual destructor.

# 7.12.4 Member Function Documentation

```
7.12.4.1 all()
```

```
bool qpp::Dynamic_bitset::all ( ) const [inline], [noexcept]
```

Checks whether all bits are set.

## Returns

True if all of the bits are set

## 7.12.4.2 any()

```
bool qpp::Dynamic_bitset::any ( ) const [inline], [noexcept]
```

Checks whether any bit is set.

#### Returns

True if any of the bits is set

# 7.12.4.3 count()

```
idx qpp::Dynamic_bitset::count ( ) const [inline], [noexcept]
```

Number of bits set to one in the bitset (Hamming weight)

#### Returns

Hamming weight

## 7.12.4.4 data()

```
const storage_type& qpp::Dynamic_bitset::data ( ) const [inline]
```

Raw storage space of the bitset.

## Returns

Const reference to the underlying storage space

# 7.12.4.5 display()

qpp::IDisplay::display() override, displays the bitset bit by bit

#### **Parameters**

os Output stream passed by reference

#### Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.12.4.6 flip() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip (
        idx pos ) [inline]
```

Flips the bit at position pos.

#### **Parameters**

pos Position in the bitset

# Returns

Reference to the current instance

```
7.12.4.7 flip() [2/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip ( ) [inline], [noexcept]
```

Flips all bits.

#### Returns

Reference to the current instance

# 7.12.4.8 get()

```
bool qpp::Dynamic_bitset::get (
          idx pos ) const [inline], [noexcept]
```

The value of the bit at position pos.

#### **Parameters**

pos	Position in the bitset
-----	------------------------

## Returns

The value of the bit at position pos

# 7.12.4.9 index\_()

Index of the pos bit in the storage space.

## **Parameters**

```
pos Bit location
```

# Returns

Index of the pos bit in the storage space

#### 7.12.4.10 none()

```
bool qpp::Dynamic_bitset::none ( ) const [inline], [noexcept]
```

Checks whether none of the bits are set.

#### Returns

True if none of the bits are set

## 7.12.4.11 offset\_()

Offset of the pos bit in the storage space relative to its index.

#### **Parameters**

```
pos Bit location
```

## Returns

Offset of the pos bit in the storage space relative to its index

## 7.12.4.12 operator"!=()

Inequality operator.

#### **Parameters**

```
rhs Dynamic_bitset against which the inequality is being tested
```

#### Returns

True if the bitsets are not equal (bit by bit), false otherwise

#### 7.12.4.13 operator-()

Number of places the two bitsets differ (Hamming distance)

## **Parameters**

rhs Dynamic\_bitset against which the Hamming distance is computed

## Returns

Hamming distance

## 7.12.4.14 operator==()

Equality operator.

#### **Parameters**

```
rhs Dynamic_bitset against which the equality is being tested
```

#### Returns

True if the bitsets are equal (bit by bit), false otherwise

## **7.12.4.15** rand() [1/2]

```
Dynamic_bitset& qpp::Dynamic_bitset::rand (
    idx pos,
    double p = 0.5 ) [inline]
```

Sets the bit at position *pos* according to a Bernoulli(p) distribution.

# **Parameters**

pos	Position in the bitset
р	Probability

#### Returns

Reference to the current instance

Sets all bits according to a Bernoulli(p) distribution.

#### **Parameters**

```
p Probability
```

#### Returns

Reference to the current instance

Sets the bit at position pos to false.

#### **Parameters**

```
pos Position in the bitset
```

# Returns

Reference to the current instance

```
7.12.4.18 reset() [2/2]
Dynamic_bitset& qpp::Dynamic_bitset::reset ( ) [inline], [noexcept]
Sets all bits to false.
```

Returns

Reference to the current instance

```
7.12.4.19 set() [1/2]
```

Sets the bit at position pos.

## **Parameters**

pos	Position in the bitset
value	Bit value

## Returns

Reference to the current instance

```
7.12.4.20 set() [2/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::set () [inline], [noexcept]
```

Set all bits to true.

## Returns

Reference to the current instance

# 7.12.4.21 size()

```
idx qpp::Dynamic_bitset::size ( ) const [inline], [noexcept]
```

Number of bits stored in the bitset.

# Returns

Number of bits stored in the bitset

#### 7.12.4.22 storage\_size()

```
idx qpp::Dynamic_bitset::storage_size ( ) const [inline], [noexcept]
```

Size of the underlying storage space (in units of value\_type, unsigned int by default)

#### Returns

Size of the underlying storage space

# 7.12.4.23 to\_string()

## String representation.

## **Template Parameters**

CharT	String character type
Traits	String traits
Allocator	String Allocator

#### **Parameters**

zero	Character representing the zero
one	Character representing the one

#### Returns

The bitset as a string

# 7.12.5 Member Data Documentation

```
7.12.5.1 n_
idx qpp::Dynamic_bitset::n_ [protected]
```

## 7.12.5.2 storage\_size\_

number of bits

```
idx qpp::Dynamic_bitset::storage_size_ [protected]
```

# storage size

```
7.12.5.3 v_
std::vector<value_type> qpp::Dynamic_bitset::v_ [protected]
storage space
```

The documentation for this class was generated from the following file:

· classes/reversible.h

# 7.13 qpp::internal::EqualEigen Class Reference

Functor for comparing Eigen expressions for equality.

```
#include <functions.h>
```

## **Public Member Functions**

template<typename Derived >
 bool operator() (const Eigen::MatrixBase< Derived > &A, const Eigen::MatrixBase< Derived > &B) const

# 7.13.1 Detailed Description

Functor for comparing Eigen expressions for equality.

Note

Works without assertion fails even if the dimensions of the arguments are different (in which case it simply returns false)

## 7.13.2 Member Function Documentation

# 7.13.2.1 operator()()

The documentation for this class was generated from the following file:

· functions.h

# 7.14 qpp::internal::EqualSameSizeStringDits Class Reference

Functor for comparing strings of numbers of equal sizes in lexicographical order. Establishes a strict weak ordering relation.

```
#include <functions.h>
```

## **Public Member Functions**

• bool operator() (const std::string &s1, const std::string &s2) const

## 7.14.1 Detailed Description

Functor for comparing strings of numbers of equal sizes in lexicographical order. Establishes a strict weak ordering relation.

Note

Used as a hash table comparator in qpp::QEngine

# 7.14.2 Member Function Documentation

# 7.14.2.1 operator()()

The documentation for this class was generated from the following file:


· functions.h

# 7.15 qpp::exception::Exception Class Reference


Base class for generating Quantum++ custom exceptions.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Exception:



Collaboration diagram for qpp::exception::Exception:



#### **Public Member Functions**

- Exception (const std::string &where)
  - Constructs an exception.
- const char \* what () const noexcept override
  - Overrides std::exception::what()
- virtual std::string description () const =0

Exception description.

# **Private Attributes**

- std::string where
- std::string msg

# 7.15.1 Detailed Description

Base class for generating Quantum++ custom exceptions.

Derive from this class if more exceptions are needed, making sure to override qpp::exception::Exception::Exception::description() in the derived class and to inherit the constructor qpp::exception::Exception::Exception(). Preferably keep your newly defined exception classes in the namespace qpp::exception.

# Example:

```
namespace qpp
{
namespace exception
{
    class ZeroSize : public Exception
    {
        public:
            std::string description() const override
            {
                  return "Object has zero size";
            }
            // inherit the base class' qpp::exception::Exception constructor using Exception::Exception;
        };
} // namespace exception
} // namespace qpp
```

#### 7.15.2 Constructor & Destructor Documentation

#### 7.15.2.1 Exception()

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred
-------	--

#### 7.15.3 Member Function Documentation

#### 7.15.3.1 description()

```
std::string qpp::exception::Exception::description ( ) const [inline], [pure virtual]
```

Exception description.

# Returns

# **Exception** description

Implemented in qpp::exception::InvalidIterator, qpp::exception::NotImplemented, qpp::exception::CustomException, qpp::exception::Duplicates, qpp::exception::QuditAlreadyMeasured, qpp::exception::UndefinedType, qpp::exception::SizeMismatch, qpp::exception::TypeMismatch, qpp::exception::OutOfRange, qpp::exception::NotOdeword, qpp::exception::NotBipartite, qpp::exception::NotQubitSubsys, qpp::exception::NotQubitVector, qpp::exception::NotQubitRvector, qpp::exception::NotQubitCvector qpp::exception::NotQubitMatrix, qpp::exception::PermMismatchDims, qpp::exception::PermInvalid, qpp::exception::SubsysMismatchEqpp::exception::DimsMismatchVector, qpp::exception::DimsMismatchCvector, qpp::exception::DimsMismatchMatrix, qpp::exception::DimsNotEqual, qpp::exception::DimsInvalid, qpp::exception::MatrixMismatchSu qpp::exception::MatrixNotSquareNorVector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::Unknown.

```
7.15.3.2 what()
```

```
const char* qpp::exception::Exception::what ( ) const [inline], [override], [noexcept]
```

Overrides std::exception::what()

#### Returns

**Exception** description

# 7.15.4 Member Data Documentation

# 7.15.4.1 msg\_

std::string qpp::exception::Exception::msg\_ [mutable], [private]

## 7.15.4.2 where\_

std::string qpp::exception::Exception::where\_ [private]

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.16 qpp::Gates Class Reference


const Singleton class that implements most commonly used gates

#include <classes/gates.h>

Inheritance diagram for qpp::Gates:



Collaboration diagram for qpp::Gates:



# **Public Member Functions**

cmat Rn (double theta, const std::vector< double > &n) const

Qubit rotation of theta about the 3-dimensional real (unit) vector n.

cmat RX (double theta) const

Qubit rotation of theta about the X axis.

cmat RY (double theta) const

Qubit rotation of theta about the Y axis.

cmat RZ (double theta) const

Qubit rotation of theta about the Z axis.

• cmat Zd (idx D=2) const

Generalized Z gate for qudits.

• cmat SWAPd (idx D=2) const

SWAP gate for qudits.

• cmat Fd (idx D=2) const

Quantum Fourier transform gate for qudits.

• cmat MODMUL (idx a, idx N, idx n) const

Modular multiplication gate for qubits Implements  $|x\rangle \longrightarrow |ax \bmod N\rangle$ .

• cmat Xd (idx D=2) const

Generalized X gate for qudits.

• template<typename Derived = Eigen::MatrixXcd>

Derived Id (idx D=2) const

Identity gate.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > CTRL (const Eigen::MatrixBase< Derived > &A, const std::vector<
idx > &ctrl, const std::vector< idx > &target, idx n, idx d=2) const

Generates the multi-partite multiple-controlled-A gate in matrix form.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$ 

dyn\_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
std::vector< idx > &dims) const

Expands out.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
std::initializer\_list< idx > &dims) const

Expands out.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, idx n,
idx d=2) const

Expands out.

std::string get\_name (const cmat &U) const

Get the name of the most common qubit gates.

#### **Public Attributes**

cmat Id2 {cmat::Identity(2, 2)}

Identity gate.

cmat H {cmat::Zero(2, 2)}

Hadamard gate.

cmat X {cmat::Zero(2, 2)}

Pauli Sigma-X gate.

cmat Y {cmat::Zero(2, 2)}

```
Pauli Sigma-Y gate.

    cmat Z {cmat::Zero(2, 2)}

     Pauli Sigma-Z gate.

    cmat S {cmat::Zero(2, 2)}

     S gate.

    cmat T {cmat::Zero(2, 2)}

      T gate.
cmat CNOT {cmat::ldentity(4, 4)}
     Controlled-NOT control target gate.
cmat CZ {cmat::Identity(4, 4)}
     Controlled-Phase gate.
cmat CNOTba {cmat::Zero(4, 4)}
     Controlled-NOT target->control gate.
• cmat SWAP {cmat::Identity(4, 4)}
     SWAP gate.
• cmat TOF {cmat::ldentity(8, 8)}
      Toffoli gate.
cmat FRED {cmat::Identity(8, 8)}
     Fredkin gate.
```

#### **Private Member Functions**

• Gates ()

Initializes the gates.

• ∼Gates ()=default

Default destructor.

# **Friends**

class internal::Singleton < const Gates >

## **Additional Inherited Members**

# 7.16.1 Detailed Description

const Singleton class that implements most commonly used gates

# 7.16.2 Constructor & Destructor Documentation

```
7.16.2.1 Gates()

qpp::Gates::Gates ( ) [inline], [private]
```

Initializes the gates.

#### 7.16.2.2 $\sim$ Gates()

```
qpp::Gates::~Gates ( ) [private], [default]
```

Default destructor.

# 7.16.3 Member Function Documentation

## 7.16.3.1 CTRL()

Generates the multi-partite multiple-controlled-A gate in matrix form.

#### See also

```
qpp::applyCTRL()
```

#### Note

The dimension of the gate A must match the dimension of target

# **Parameters**

Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
n	Total number of subsystems
d	Subsystem dimensions

#### Returns

CTRL-A gate, as a matrix over the same scalar field as A

## 7.16.3.2 expandout() [1/3]

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::Gates::expandout (
```

```
const Eigen::MatrixBase< Derived > & A,
idx pos,
const std::vector< idx > & dims ) const [inline]
```

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

#### **Parameters**

Α	Eigen expression
pos	Position
dims	Dimensions of the multi-partite system

## Returns

Tensor product  $I \otimes \cdots \otimes I \otimes A \otimes I \otimes \cdots \otimes I$ , with A on position pos, as a dynamic matrix over the same scalar field as A

#### 7.16.3.3 expandout() [2/3]

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Note

The std::initializer\_list overload exists because otherwise, in the degenerate case when *dims* has only one element, the one element list is implicitly converted to the element's underlying type, i.e. <a href="qpp::idx">qpp::idx</a>, which has the net effect of picking the wrong (non-vector) <a href="qpp::expandout">qpp::expandout</a>() overload

#### **Parameters**

Α	Eigen expression
pos	Position
dims	Dimensions of the multi-partite system

#### Returns

Tensor product  $I\otimes\cdots\otimes I\otimes A\otimes I\otimes\cdots\otimes I$ , with A on position pos, as a dynamic matrix over the same scalar field as A

#### 7.16.3.4 expandout() [3/3]

Expands out.

#### See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

## **Parameters**

Α	Eigen expression
pos	Position
n	Number of subsystems
d	Subsystem dimensions

# Returns

Tensor product  $I \otimes \cdots \otimes I \otimes A \otimes I \otimes \cdots \otimes I$ , with A on position pos, as a dynamic matrix over the same scalar field as A

# 7.16.3.5 Fd()

```
cmat qpp::Gates::Fd (
    idx D = 2 ) const [inline]
```

Quantum Fourier transform gate for qudits.

#### Note

```
Defined as F = \sum_{j,k=0}^{D-1} \exp(2\pi \mathrm{i} jk/D) |j\rangle\langle k|
```

#### **Parameters**

D Dimension of the Hilbert space

## Returns

Fourier transform gate for qudits

#### 7.16.3.6 get\_name()

Get the name of the most common qubit gates.

Note

Assumes that the gate U is represented by a square matrix. If not, returns the empty string

#### **Parameters**

U Complex matrix representing the quantum gate

# Returns

The name of the gate (if any), otherwise the empty string

# 7.16.3.7 Id()

```
template<typename Derived = Eigen::MatrixXcd>
Derived qpp::Gates::Id (
    idx D = 2 ) const [inline]
```

Identity gate.

Note

Can change the return type from complex matrix (default) by explicitly specifying the template parameter

#### **Parameters**

D | Dimension of the Hilbert space

#### Returns

Identity gate on a Hilbert space of dimension D

# 7.16.3.8 MODMUL()

```
cmat qpp::Gates::MODMUL (
          idx a,
          idx N,
          idx n ) const [inline]
```

Modular multiplication gate for qubits Implements  $|x\rangle \longrightarrow |ax \mathrm{mod} N\rangle$ .

#### Note

For the gate to be unitary, *a* and *N* should be co-prime. The function does not check co-primality in release versions!

The number of qubits required to implement the gate should satisfy  $n \geq \lceil \log_2(N) \rceil$ 

#### **Parameters**

а	Positive integer less than N
Ν	Positive integer
n	Number of qubits required for implementing the gate

#### Returns

Modular multiplication gate

# 7.16.3.9 Rn()

Qubit rotation of *theta* about the 3-dimensional real (unit) vector *n*.

#### **Parameters**

theta	Rotation angle
n	3-dimensional real (unit) vector

# Returns

Rotation gate

## 7.16.3.10 RX()

Qubit rotation of theta about the X axis.

#### **Parameters**

theta	Rotation angle
-------	----------------

# Returns

Rotation gate

# 7.16.3.11 RY()

Qubit rotation of theta about the Y axis.

# **Parameters**

theta Rotation angle
----------------------

#### Returns

Rotation gate

# 7.16.3.12 RZ()

Qubit rotation of theta about the Z axis.

# **Parameters**

theta	Rotation angle

Returns

Rotation gate

# 7.16.3.13 SWAPd()

```
cmat qpp::Gates::SWAPd (
    idx D = 2 ) const [inline]
```

SWAP gate for qudits.

#### **Parameters**

D Dimension of the Hilbert space

## Returns

SWAP gate for qudits

# 7.16.3.14 Xd()

```
cmat qpp::Gates::Xd (
    idx D = 2 ) const [inline]
```

Generalized X gate for qudits.

Note

```
Defined as X=\sum_{j=0}^{D-1}|j\oplus 1\rangle\langle j|, i.e. raising operator X|j\rangle=|j\oplus 1\rangle
```

# **Parameters**

D Dimension of the Hilbert space

## Returns

Generalized X gate for qudits

# 7.16.3.15 Zd()

```
cmat qpp::Gates::Zd (
        idx D = 2 ) const [inline]
```

Generalized Z gate for qudits.

Note

```
Defined as Z = \sum_{j=0}^{D-1} \exp(2\pi \mathrm{i} j/D) |j\rangle\langle j|
```

#### **Parameters**

D Dimension of the Hilbert space

## Returns

Generalized Z gate for qudits

#### 7.16.4 Friends And Related Function Documentation

```
7.16.4.1 internal::Singleton < const Gates >
```

```
friend class internal::Singleton< const Gates > [friend]
```

## 7.16.5 Member Data Documentation

## 7.16.5.1 CNOT

```
cmat qpp::Gates::CNOT {cmat::Identity(4, 4)}
```

Controlled-NOT control target gate.

#### 7.16.5.2 CNOTba

```
cmat qpp::Gates::CNOTba {cmat::Zero(4, 4)}
```

Controlled-NOT target->control gate.

#### 7.16.5.3 CZ

```
cmat qpp::Gates::CZ {cmat::Identity(4, 4)}
```

Controlled-Phase gate.

```
7.16.5.4 FRED
cmat qpp::Gates::FRED {cmat::Identity(8, 8)}
Fredkin gate.
7.16.5.5 H
cmat qpp::Gates::H {cmat::Zero(2, 2)}
Hadamard gate.
7.16.5.6 Id2
cmat qpp::Gates::Id2 {cmat::Identity(2, 2)}
Identity gate.
7.16.5.7 S
cmat qpp::Gates::S {cmat::Zero(2, 2)}
S gate.
7.16.5.8 SWAP
cmat qpp::Gates::SWAP {cmat::Identity(4, 4)}
SWAP gate.
7.16.5.9 T
cmat qpp::Gates::T {cmat::Zero(2, 2)}
```

T gate.

```
7.16.5.10 TOF
```

```
cmat qpp::Gates::TOF {cmat::Identity(8, 8)}
```

Toffoli gate.

7.16.5.11 X

```
cmat qpp::Gates::X {cmat::Zero(2, 2)}
```

Pauli Sigma-X gate.

7.16.5.12 Y

```
cmat qpp::Gates::Y {cmat::Zero(2, 2)}
```

Pauli Sigma-Y gate.

7.16.5.13 Z

```
cmat qpp::Gates::Z {cmat::Zero(2, 2)}
```

Pauli Sigma-Z gate.

The documentation for this class was generated from the following file:


classes/gates.h

# 7.17 qpp::QCircuit::GateStep Struct Reference

One step consisting only of gates/operators in the circuit.

```
#include <classes/circuits/circuits.h>
```

Collaboration diagram for qpp::QCircuit::GateStep:



## **Public Member Functions**

• GateStep ()=default

Default constructor.

GateStep (GateType gate\_type, std::size\_t gate\_hash, const std::vector < idx > &ctrl, const std::vector < idx > &trl, const std::vector < idx > &target, std::string name={})

Constructs a gate step instance.

## **Public Attributes**

```
GateType gate_type_ = GateType::NONE
```

gate type

std::size\_t gate\_hash\_ {}

gate hash

std::vector< idx > ctrl\_ {}

control

std::vector< idx > target\_{}{}

target where the gate is applied

std::string name\_{}{}

custom name of the step

## 7.17.1 Detailed Description

One step consisting only of gates/operators in the circuit.

## 7.17.2 Constructor & Destructor Documentation

```
7.17.2.1 GateStep() [1/2]

qpp::QCircuit::GateStep::GateStep ( ) [default]
```

Default constructor.

### 7.17.2.2 GateStep() [2/2]

```
qpp::QCircuit::GateStep::GateStep (
    GateType gate_type,
    std::size_t gate_hash,
    const std::vector< idx > & ctrl,
    const std::vector< idx > & target,
    std::string name = {} ) [inline], [explicit]
```

Constructs a gate step instance.

### **Parameters**

control

gate_type	Gate type
gate_hash	Hash of the quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes
name	Optional gate name

### 7.17.3 Member Data Documentation

```
7.17.3.1 ctrl_
std::vector<idx> qpp::QCircuit::GateStep::ctrl_ {}
```

```
7.17.3.2 gate_hash_
std::size_t qpp::QCircuit::GateStep::gate_hash_ {}
gate hash
7.17.3.3 gate_type_
GateType qpp::QCircuit::GateStep::gate_type_ = GateType::NONE
gate type
7.17.3.4 name_
std::string qpp::QCircuit::GateStep::name_ {}
custom name of the step
7.17.3.5 target_
std::vector<idx> qpp::QCircuit::GateStep::target_ {}
```

target where the gate is applied

The documentation for this struct was generated from the following file:

· classes/circuits/circuits.h

# 7.18 qpp::internal::HashEigen Class Reference

Functor for hashing Eigen expressions.

```
#include <functions.h>
```

## **Public Member Functions**

template < typename Derived >
 std::size\_t operator() (const Eigen::MatrixBase < Derived > &A) const

## 7.18.1 Detailed Description

Functor for hashing Eigen expressions.

## 7.18.2 Member Function Documentation

## 7.18.2.1 operator()()

The documentation for this class was generated from the following file:


· functions.h

# 7.19 qpp::IDisplay Class Reference

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

```
#include <classes/idisplay.h>
```

Inheritance diagram for qpp::IDisplay:



### **Public Member Functions**

virtual ~IDisplay ()=default
 Default virtual destructor.

### **Private Member Functions**

virtual std::ostream & display (std::ostream &os) const =0
 Must be overridden by all derived classes.

### **Friends**

std::ostream & operator<< (std::ostream &os, const IDisplay &rhs)</li>
 Overloads the extraction operator.

## 7.19.1 Detailed Description

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

This class defines friend std::ostream& operator<<(std::ostream& os, const qpp::IDisplay& rhs). The latter delegates the work to the pure private virtual function qpp::IDisplay::display() which has to be overridden by all derived classes.

### 7.19.2 Constructor & Destructor Documentation

```
7.19.2.1 ~IDisplay()

virtual qpp::IDisplay::~IDisplay ( ) [virtual], [default]

Default virtual destructor.
```

## 7.19.3 Member Function Documentation

```
7.19.3.1 display()
```

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implemented in qpp::QCircuit, qpp::QEngine, qpp::QCircuit::iterator::value\_type\_, qpp::Dynamic\_bitset, qpp::internal::IOManipEigen, qpp::Timer< T, CLOCK\_T >, qpp::internal::IOManipPointer< PointerType >, and qpp::internal::IOManipRange< InputIterator >.

## 7.19.4 Friends And Related Function Documentation

### 7.19.4.1 operator <<

Overloads the extraction operator.

Delegates the work to the virtual function <a href="mailto:qpp::IDisplay::display">qpp::IDisplay::display()</a>

The documentation for this class was generated from the following file:


· classes/idisplay.h

# 7.20 qpp::IJSON Class Reference

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

```
#include <classes/idisplay.h>
```

Inheritance diagram for qpp::IJSON:



## **Public Member Functions**

- virtual  $\sim$ IJSON ()=default
  - Default virtual destructor.
- virtual std::string to\_JSON (bool enclosed\_in\_curly\_brackets=true) const =0
   JSON representation of the derived instance, must be overridden by all derived classes.

## 7.20.1 Detailed Description

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

## 7.20.2 Constructor & Destructor Documentation

```
7.20.2.1 \simIJSON() virtual qpp::IJSON::\simIJSON ( ) [virtual], [default]
```

## 7.20.3 Member Function Documentation

Default virtual destructor.

JSON representation of the derived instance, must be overridden by all derived classes.

## **Parameters**

enclosed_in_curly_brackets   If true, encloses the result in curly
--

Implemented in qpp::QCircuit, and qpp::QEngine.

The documentation for this class was generated from the following file:


· classes/idisplay.h

## 7.21 qpp::Init Class Reference


const Singleton class that performs additional initializations/cleanups

```
#include <classes/init.h>
```

Inheritance diagram for qpp::Init:



Collaboration diagram for qpp::Init:



## **Private Member Functions**

- Init ()
  - Additional initializations.
- ∼Init ()

Cleanups.

## **Friends**

class internal::Singleton < const Init >

## **Additional Inherited Members**

## 7.21.1 Detailed Description

const Singleton class that performs additional initializations/cleanups

## 7.21.2 Constructor & Destructor Documentation

```
7.21.2.1 Init()

qpp::Init::Init ( ) [inline], [private]

Additional initializations.
```

```
7.21.2.2 ∼Init()
```

```
qpp::Init::~Init ( ) [inline], [private]
```

Cleanups.

### 7.21.3 Friends And Related Function Documentation

```
7.21.3.1 internal::Singleton < const Init >
```

```
friend class internal::Singleton< const Init > [friend]
```

The documentation for this class was generated from the following file:


· classes/init.h

# 7.22 qpp::exception::InvalidIterator Class Reference


Invalid iterator.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::InvalidIterator:



Collaboration diagram for qpp::exception::InvalidIterator:



## **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

## 7.22.1 Detailed Description

Invalid iterator.

## 7.22.2 Member Function Documentation

## 7.22.2.1 description()

```
std::string qpp::exception::InvalidIterator::description ( ) const [inline], [override],
[virtual]
```

Exception description.

### Returns

**Exception** description

Implements qpp::exception::Exception.

## 7.22.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

## **Parameters**

where	,	Text representing where the exception occurred
-------	---	--


The documentation for this class was generated from the following file:

· classes/exception.h


# 7.23 qpp::internal::IOManipEigen Class Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipEigen:



Collaboration diagram for qpp::internal::IOManipEigen:



## **Public Member Functions**

- template<typename Derived >
   IOManipEigen (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
- IOManipEigen (const cplx z, double chop=qpp::chop)

## **Private Member Functions**

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

## **Private Attributes**

- cmat A\_
- double chop\_

### 7.23.1 Constructor & Destructor Documentation

### 7.23.2 Member Function Documentation

```
7.23.2.1 display()
```

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

## 7.23.3 Member Data Documentation

### 7.23.3.1 A\_

```
cmat qpp::internal::IOManipEigen::A_ [private]
```

7.23.3.2 chop\_

double qpp::internal::IOManipEigen::chop\_ [private]


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


# 7.24 qpp::internal::IOManipPointer< PointerType > Class Template Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipPointer< PointerType >:



Collaboration diagram for qpp::internal::IOManipPointer< PointerType >:



### **Public Member Functions**

- IOManipPointer (const PointerType \*p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)
- IOManipPointer (const IOManipPointer &)=default
- IOManipPointer & operator= (const IOManipPointer &)=default

## **Private Member Functions**

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

### **Private Attributes**

- const PointerType \* p\_
- idx N
- std::string separator\_
- std::string start
- std::string end
- double chop\_

#### 7.24.1 Constructor & Destructor Documentation

```
7.24.1.1 IOManipPointer() [1/2]
```

## 7.24.1.2 | IOManipPointer() [2/2]

## 7.24.2 Member Function Documentation

### 7.24.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

## 7.24.2.2 operator=()

### 7.24.3 Member Data Documentation

```
7.24.3.1 chop_
```

```
template<typename PointerType >
double qpp::internal::IOManipPointer< PointerType >::chop_ [private]
```

### 7.24.3.2 end\_

```
template<typename PointerType >
std::string qpp::internal::IOManipPointer< PointerType >::end_ [private]
```

## 7.24.3.3 N\_

```
template<typename PointerType >
idx qpp::internal::IOManipPointer< PointerType >::N_ [private]
```

## 7.24.3.4 p\_

```
template<typename PointerType >
const PointerType* qpp::internal::IOManipPointer< PointerType >::p_ [private]
```

#### 7.24.3.5 separator

```
template<typename PointerType >
std::string qpp::internal::IOManipPointer< PointerType >::separator_ [private]
```

### 7.24.3.6 start\_

```
template<typename PointerType >
std::string qpp::internal::IOManipPointer< PointerType >::start_ [private]
```


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


## 7.25 qpp::internal::IOManipRange < InputIterator > Class Template Reference

```
#include <internal/classes/iomanip.h>
```

Inheritance diagram for qpp::internal::IOManipRange< InputIterator >:



Collaboration diagram for qpp::internal::IOManipRange< InputIterator >:



## **Public Member Functions**

- IOManipRange (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)
- IOManipRange (const IOManipRange &)=default
- IOManipRange & operator= (const IOManipRange &)=default

## **Private Member Functions**

• std::ostream & display (std::ostream &os) const override

Must be overridden by all derived classes.

## **Private Attributes**

- InputIterator first\_
- InputIterator last\_
- std::string separator\_
- std::string start\_
- std::string end\_
- double chop\_

## 7.25.1 Constructor & Destructor Documentation

### 7.25.1.1 | IOManipRange() [1/2]

### 7.25.1.2 IOManipRange() [2/2]

### 7.25.2 Member Function Documentation

## 7.25.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

### 7.25.2.2 operator=()

### 7.25.3 Member Data Documentation

```
7.25.3.1 chop_
template<typename InputIterator >
double qpp::internal::IOManipRange< InputIterator >::chop_ [private]
7.25.3.2 end
{\tt template}{<}{\tt typename~InputIterator~>}
std::string qpp::internal::IOManipRange< InputIterator >::end_ [private]
7.25.3.3 first_
template<typename InputIterator >
InputIterator qpp::internal::IOManipRange< InputIterator >::first_ [private]
7.25.3.4 last
{\tt template}{<}{\tt typename \ InputIterator} >
InputIterator qpp::internal::IOManipRange< InputIterator >::last_ [private]
7.25.3.5 separator_
template<typename InputIterator >
std::string qpp::internal::IOManipRange< InputIterator >::separator_ [private]
7.25.3.6 start_
{\tt template}{<}{\tt typename~InputIterator~>}
std::string qpp::internal::IOManipRange< InputIterator >::start_ [private]
```

The documentation for this class was generated from the following file:

internal/classes/iomanip.h

# 7.26 qpp::is\_complex< T > Struct Template Reference


Checks whether the type is a complex type.

#include <traits.h>

Inheritance diagram for qpp::is\_complex< T >:



Collaboration diagram for qpp::is\_complex< T >:



## 7.26.1 Detailed Description

template<typename T> struct qpp::is\_complex< T>

Checks whether the type is a complex type.

Provides the constant member *value* which is equal to *true*, if the type is a complex type, i.e. *std::complex<T>* 

The documentation for this struct was generated from the following file:

· traits.h

# 7.27 qpp::is\_complex < std::complex < T > > Struct Template Reference


Checks whether the type is a complex number type, specialization for complex types.

```
#include <traits.h>
```

Inheritance diagram for qpp::is\_complex < std::complex < T > :



Collaboration diagram for qpp::is\_complex< std::complex< T >>:



## 7.27.1 Detailed Description

```
template<typename T> struct qpp::is_complex< std::complex< T > >
```

Checks whether the type is a complex number type, specialization for complex types.

The documentation for this struct was generated from the following file:


· traits.h

# 7.28 qpp::is\_iterable < T, typename > Struct Template Reference


Checks whether T is compatible with an STL-like iterable container.

#include <traits.h>

Inheritance diagram for qpp::is\_iterable < T, typename >:



Collaboration diagram for qpp::is\_iterable < T, typename >:



## 7.28.1 Detailed Description

template<typename T, typename = void> struct qpp::is\_iterable< T, typename >

Checks whether T is compatible with an STL-like iterable container.

Provides the constant member *value* which is equal to *true*, if *T* is compatible with an iterable container, i.e. provides at least *begin()* and *end()* member functions and allows de-referencing. Otherwise, *value* is equal to *false*.

The documentation for this struct was generated from the following file:


· traits.h

7.29 qpp::is\_iterable < T, to\_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().begin())) > Struct Template Reference

Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

```
#include <traits.h>
```

Inheritance diagram for qpp::is\_iterable < T, to\_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(\*(std::declval < T >().begin())) > :



 $\label{eq:control_control_control} \mbox{Collaboration diagram for qpp::is\_iterable} < \mbox{T, to\_void} < \mbox{decltype(std::declval} < \mbox{T} > ().begin()), \mbox{decltype(std::declval} < \mbox{T} > ().begin())) > : \\ \mbox{control_control$ 



## 7.29.1 Detailed Description

 $template < typename \ T > \\ struct \ qpp::is\_iterable < T, \ to\_void < decltype(std::declval < T > ().begin()), \ decltype(std::declval < T > ().end()), \ decltype(*(std::declval < T > ().begin())) > \\ ::declval < T > ().begin())) > \\$ 

Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

The documentation for this struct was generated from the following file:

· traits.h

## 7.30 qpp::is\_matrix\_expression < Derived > Struct Template Reference


Checks whether the type is an Eigen matrix expression.

```
#include <traits.h>
```

Inheritance diagram for qpp::is\_matrix\_expression< Derived >:



Collaboration diagram for qpp::is\_matrix\_expression< Derived >:



## 7.30.1 Detailed Description

template < typename Derived > struct qpp::is\_matrix\_expression < Derived >

Checks whether the type is an Eigen matrix expression.

Provides the constant member *value* which is equal to *true*, if the type is an Eigen matrix expression of type *Eigen* :: *MatrixBase* < *Derived* >. Otherwise, *value* is equal to *false*.

The documentation for this struct was generated from the following file:


traits.h

# 7.31 qpp::QCircuit::iterator Class Reference

Quantum circuit bound-checking (safe) iterator.

#include <classes/circuits/circuits.h>

Collaboration diagram for qpp::QCircuit::iterator:



## Classes

· class value\_type\_

Value type class for qpp::QCircuit::iterator.

## **Public Types**

• using difference\_type = long long

iterator trait

• using value\_type = value\_type\_

iterator trait

using pointer = const value\_type \*

iterator trait

• using reference = const value\_type &

iterator trait

using iterator\_category = std::forward\_iterator\_tag

iterator trait

## **Public Member Functions**

• iterator ()=default

Default constructor.

• iterator (const iterator &)=default

Default copy constructor.

• iterator & operator= (const iterator &)=default

Default copy assignment operator.

iterator & operator++ ()

Prefix increment operator.

• iterator operator++ (int)

Postfix increment operator.

- bool operator== (const iterator &rhs) const Equality operator.
- bool operator!= (iterator rhs) const Inequality operator.
- const value\_type\_ & operator \* () const

Safe de-referencing operator.

void set\_begin\_ (const QCircuit \*qc)

Sets the iterator to std::begin(this)

void set\_end\_ (const QCircuit \*qc)

Sets the iterator to std::begin(this)

#### **Private Attributes**

```
const QCircuit * qc_ {nullptr}
```

< non-owning pointer to the parent const quantum circuit

value\_type\_ elem\_ {nullptr}

## 7.31.1 Detailed Description

Quantum circuit bound-checking (safe) iterator.

Note

The iterator is a const\_iterator by default

## 7.31.2 Member Typedef Documentation

## 7.31.2.1 difference\_type

```
using qpp::QCircuit::iterator::difference_type = long long
```

iterator trait

## 7.31.2.2 iterator\_category

```
using qpp::QCircuit::iterator::iterator_category = std::forward_iterator_tag
```

iterator trait

```
7.31.2.3 pointer
using qpp::QCircuit::iterator::pointer = const value_type*
iterator trait
7.31.2.4 reference
using qpp::QCircuit::iterator::reference = const value_type&
iterator trait
7.31.2.5 value_type
using qpp::QCircuit::iterator::value_type = value_type_
iterator trait
7.31.3 Constructor & Destructor Documentation
7.31.3.1 iterator() [1/2]
qpp::QCircuit::iterator::iterator ( ) [default]
Default constructor.
7.31.3.2 iterator() [2/2]
qpp::QCircuit::iterator::iterator (
```

Default copy constructor.

## 7.31.4 Member Function Documentation

const iterator & ) [default]

```
7.31.4.1 operator *()
```

```
const value_type_& qpp::QCircuit::iterator::operator * ( ) const [inline]
```

Safe de-referencing operator.

Returns

Constant reference to the iterator element

## 7.31.4.2 operator"!=()

Inequality operator.

### **Parameters**

rhs Iterator against which the inequality is being tested

Returns

True if the iterators are not equal (bit by bit), false otherwise

```
7.31.4.3 operator++() [1/2]
```

```
iterator& qpp::QCircuit::iterator::operator++ ( ) [inline]
```

Prefix increment operator.

Returns

Reference to the current instance

```
7.31.4.4 operator++() [2/2]
```

Postfix increment operator.

Returns

Copy of the current instance before the increment

```
7.31.4.5 operator=()
```

Default copy assignment operator.

Returns

Reference to the current instance

```
7.31.4.6 operator==()
```

Equality operator.

**Parameters** 

rhs | Iterator against which the equality is being tested

Returns

True if the iterators are equal, false otherwise

```
7.31.4.7 set_begin_()
```

Sets the iterator to std::begin(this)

**Parameters** 

qc | Pointer to constant quantum circuit

```
7.31.4.8 set_end_()
```

Sets the iterator to std::begin(this)

#### **Parameters**

qc Pointer to constant quantum circuit

### 7.31.5 Member Data Documentation

```
7.31.5.1 elem_
value_type_ qpp::QCircuit::iterator::elem_ {nullptr} [private]

7.31.5.2 qc_
const QCircuit* qpp::QCircuit::iterator::qc_ {nullptr} [private]
```

< non-owning pointer to the parent const quantum circuit

The documentation for this class was generated from the following file:

· classes/circuits/circuits.h

# 7.32 qpp::make\_void < Ts > Struct Template Reference

Helper for <a href="mailto:qpp::to\_void">qpp::to\_void<>> alias template.</a>

```
#include <traits.h>
```

## **Public Types**

• typedef void type

## 7.32.1 Detailed Description

```
template<typename... Ts>
struct qpp::make_void< Ts>
```

Helper for <a href="mailto:qpp::to\_void">qpp::to\_void<>> alias template.</a>

See also

qpp::to\_void<>

## 7.32.2 Member Typedef Documentation

## 7.32.2.1 type

```
template<typename... Ts>
typedef void qpp::make_void< Ts >::type
```

The documentation for this struct was generated from the following file:


· traits.h

# 7.33 qpp::exception::MatrixMismatchSubsys Class Reference


Matrix mismatch subsystems exception.

```
#include <classes/exception.h>
```

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Mismatch Subsys:$ 



Collaboration diagram for qpp::exception::MatrixMismatchSubsys:



## **Public Member Functions**

- std::string description () const override
  - Exception description.
- Exception (const std::string &where)

Constructs an exception.

## 7.33.1 Detailed Description

Matrix mismatch subsystems exception.

Matrix size mismatch subsystem sizes (e.g. in qpp::apply())

## 7.33.2 Member Function Documentation

## 7.33.2.1 description()

std::string qpp::exception::MatrixMismatchSubsys::description ( ) const [inline], [override],
[virtual]

Exception description.

## Returns

**Exception** description

Implements qpp::exception::Exception.

## 7.33.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

### **Parameters**

where Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.34 qpp::exception::MatrixNotCvector Class Reference


Matrix is not a column vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotCvector:



Collaboration diagram for qpp::exception::MatrixNotCvector:



## **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

## 7.34.1 Detailed Description

Matrix is not a column vector exception.

Eigen::Matrix is not a column vector

## 7.34.2 Member Function Documentation

## 7.34.2.1 description()

```
std::string qpp::exception::MatrixNotCvector::description ( ) const [inline], [override],
[virtual]
```

Exception description.

### Returns

**Exception** description

Implements qpp::exception::Exception.

## 7.34.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

### **Parameters**

where	Text representing where the exception occurred	
-------	--	--

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.35 qpp::exception::MatrixNotRvector Class Reference


Matrix is not a row vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotRvector:



Collaboration diagram for qpp::exception::MatrixNotRvector:



# **Public Member Functions**

Exception description.

• Exception (const std::string &where)

Constructs an exception.

# 7.35.1 Detailed Description

Matrix is not a row vector exception.

Eigen::Matrix is not a row vector

# 7.35.2 Member Function Documentation

## 7.35.2.1 description()

```
std::string qpp::exception::MatrixNotRvector::description ( ) const [inline], [override],
[virtual]
```

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

## 7.35.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where Text representing where the exception occurre	d
---	---

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.36 qpp::exception::MatrixNotSquare Class Reference


Matrix is not square exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquare:



Collaboration diagram for qpp::exception::MatrixNotSquare:



# **Public Member Functions**

Exception description.

• Exception (const std::string &where)

Constructs an exception.

# 7.36.1 Detailed Description

Matrix is not square exception.

Eigen::Matrix is not a square matrix

# 7.36.2 Member Function Documentation

## 7.36.2.1 description()

```
std::string qpp::exception::MatrixNotSquare::description ( ) const [inline], [override],
[virtual]
```

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

## 7.36.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where Text representing where the exception occurre	d
---	---

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.37 qpp::exception::MatrixNotSquareNorCvector Class Reference


Matrix is not square nor column vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorCvector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorCvector:



# **Public Member Functions**

Exception description.

• Exception (const std::string &where)

Constructs an exception.

# 7.37.1 Detailed Description

Matrix is not square nor column vector exception.

Eigen::Matrix is not a square matrix nor a column vector

# 7.37.2 Member Function Documentation

## 7.37.2.1 description()

std::string qpp::exception::MatrixNotSquareNorCvector::description ( ) const [inline], [override],
[virtual]

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

## 7.37.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred	]
-------	--	---

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.38 qpp::exception::MatrixNotSquareNorRvector Class Reference


Matrix is not square nor row vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorRvector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorRvector:



# **Public Member Functions**

Exception description.

• Exception (const std::string &where)

Constructs an exception.

# 7.38.1 Detailed Description

Matrix is not square nor row vector exception.

Eigen::Matrix is not a square matrix nor a row vector

# 7.38.2 Member Function Documentation

## 7.38.2.1 description()

std::string qpp::exception::MatrixNotSquareNorRvector::description ( ) const [inline], [override],
[virtual]

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

## 7.38.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred	
-------	--	--

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.39 qpp::exception::MatrixNotSquareNorVector Class Reference


Matrix is not square nor vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorVector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorVector:



# **Public Member Functions**

Exception description.

• Exception (const std::string &where)

Constructs an exception.

# 7.39.1 Detailed Description

Matrix is not square nor vector exception.

Eigen::Matrix is not a square matrix nor a row/column vector

# 7.39.2 Member Function Documentation

## 7.39.2.1 description()

std::string qpp::exception::MatrixNotSquareNorVector::description ( ) const [inline], [override],
[virtual]

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

## 7.39.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

# **Parameters**

where	Text representing where the exception occurred	]
-------	--	---

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.40 qpp::exception::MatrixNotVector Class Reference


Matrix is not a vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotVector:



Collaboration diagram for qpp::exception::MatrixNotVector:



# **Public Member Functions**

Exception description.

• Exception (const std::string &where)

Constructs an exception.

# 7.40.1 Detailed Description

Matrix is not a vector exception.

Eigen::Matrix is not a row or column vector

# 7.40.2 Member Function Documentation

## 7.40.2.1 description()

```
std::string qpp::exception::MatrixNotVector::description ( ) const [inline], [override],
[virtual]
```

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

## 7.40.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

# **Parameters**

where	Text representing where the exception occurred	
-------	--	--

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.41 qpp::QCircuit::MeasureStep Struct Reference

One step consisting only of measurements in the circuit.

#include <classes/circuits/circuits.h>

Collaboration diagram for qpp::QCircuit::MeasureStep:



## **Public Member Functions**

• MeasureStep ()=default

Default constructor.

MeasureStep (MeasureType measurement\_type, const std::vector< std::size\_t > &mats\_hash, const std
 ::vector< idx > &target, idx c\_reg, std::string name={})

Constructs a measurement step instance.

## **Public Attributes**

MeasureType measurement\_type\_ = MeasureType::NONE

measurement type

- std::vector< std::size\_t >  $mats\_hash\_$  {}
- std::vector< idx > target\_{}{}

target where the measurement is applied

- idx c\_reg\_ {}

custom name of the step

## 7.41.1 Detailed Description

One step consisting only of measurements in the circuit.

#### 7.41.2 Constructor & Destructor Documentation

```
7.41.2.1 MeasureStep() [1/2]
```

```
qpp::QCircuit::MeasureStep::MeasureStep ( ) [default]
```

Default constructor.

```
7.41.2.2 MeasureStep() [2/2]
```

Constructs a measurement step instance.

#### **Parameters**

measurement_type	Measurement type
mats_hash	Vector of hashes of the measurement matrix/matrices
target	Target qudit indexes
c_reg	Classical register where the value of the measurement is stored
name	Optional gate name

#### 7.41.3 Member Data Documentation

```
7.41.3.1 c_reg_
```

```
idx qpp::QCircuit::MeasureStep::c_reg_ {}
```

index of the classical register where the measurement result is being stored

```
7.41.3.2 mats_hash_
```

```
std::vector<std::size_t> qpp::QCircuit::MeasureStep::mats_hash_ {}
```

hashes of measurement matrix/matrices

## 7.41.3.3 measurement\_type\_

```
MeasureType qpp::QCircuit::MeasureStep::measurement_type_ = MeasureType::NONE
```

measurement type

```
7.41.3.4 name_
```

```
std::string qpp::QCircuit::MeasureStep::name_ {}
```

custom name of the step

# 7.41.3.5 target\_

```
std::vector<idx> qpp::QCircuit::MeasureStep::target_ {}
```

target where the measurement is applied

The documentation for this struct was generated from the following file:


· classes/circuits/circuits.h

# 7.42 qpp::exception::NoCodeword Class Reference


Codeword does not exist exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::NoCodeword:



Collaboration diagram for qpp::exception::NoCodeword:



#### **Public Member Functions**

- std::string description () const override
  - Exception description.
- Exception (const std::string &where)

Constructs an exception.

# 7.42.1 Detailed Description

Codeword does not exist exception.

Codeword does not exist, thrown when calling qpp::Codes::codeword() with an invalid index

## 7.42.2 Member Function Documentation

# 7.42.2.1 description()

std::string qpp::exception::NoCodeword::description ( ) const [inline], [override], [virtual]
Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

#### 7.42.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.43 qpp::NoiseBase < T > Class Template Reference

Base class for all noise models, derive your particular noise model.

#include <classes/noise.h>

Collaboration diagram for qpp::NoiseBase< T >:



## **Public Types**

• using noise\_type = T

## **Public Member Functions**

template<typename U = noise\_type>
 NoiseBase (const std::vector< cmat > &Ks, typename std::enable\_if< std::is\_same< NoiseType::StateDependent,
 U >::value >::type \*=nullptr)

Constructs a noise instance for StateDependent noise type.

• template<typename U = noise\_type>

NoiseBase (const std::vector< cmat > &Ks, const std::vector< double > &probs, typename std::enable\_if< std::is\_same< NoiseType::StateIndependent, U >::value >::type \*=nullptr)

Constructs a noise instance for StateIndependent noise type.

virtual ∼NoiseBase ()=default

Default virtual destructor.

idx get d () const noexcept

Qudit dimension.

std::vector < cmat > get\_Ks () const

Vector of noise operators.

• std::vector< double > get\_probs () const

Vector of probabilities corresponding to each noise operator.

idx get\_last\_idx () const

Index of the last occurring noise element.

double get\_last\_p () const

Probability of the last occurring noise element.

cmat get\_last\_K () const

Last occurring noise element.

virtual cmat operator() (const cmat &state) const

Function invocation operator, applies the underlying noise model on the state vector or density matrix state.

· virtual cmat operator() (const cmat &state, idx target) const

Function invocation operator, applies the underlying noise model on qudit target of the multi-partite state vector or density matrix state.

virtual cmat operator() (const cmat &state, const std::vector < idx > &target) const

Function invocation operator, applies the underlying correlated noise model on qudits specified by target of the multipartite state vector or density matrix state.

#### **Protected Member Functions**

void compute\_probs\_ (const cmat &state, const std::vector < idx > &target) const

Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

• cmat compute\_state\_ (const cmat &state, const std::vector < idx > &target) const

Compute the resulting state after the noise was applied.

# **Protected Attributes**

const std::vector< cmat > Ks\_

Kraus operators.

std::vector< double > probs

probabilities

idx d\_{{}}

qudit dimension

idx i\_ {}

index of the last occurring noise element

bool generated\_ {false}

invoked, or if the noise is state-independent

# 7.43.1 Detailed Description

```
\label{eq:template} \begin{split} \text{template} &< \text{class T}> \\ \text{class qpp::NoiseBase} &< \text{T}> \end{split}
```

Base class for all noise models, derive your particular noise model.

# 7.43.2 Member Typedef Documentation

# 7.43.2.1 noise\_type

```
template<class T>
using qpp::NoiseBase< T >::noise_type = T
```

## 7.43.3 Constructor & Destructor Documentation

## 7.43.3.1 NoiseBase() [1/2]

Constructs a noise instance for StateDependent noise type.

Note

SFINAEd-out for StateIndependent noise

#### **Parameters**

Ks | Vector of noise (Kraus) operators that specify the noise

## 7.43.3.2 NoiseBase() [2/2]

```
template<class T>
template<typename U = noise_type>
```

Constructs a noise instance for StateIndependent noise type.

Note

SFINAEd-out for StateDependent noise

#### **Parameters**

Ks	Vector of noise (Kraus) operators that specify the noise
probs	Vector of probabilities corresponding to each Kraus operator

## 7.43.3.3 ∼NoiseBase()

```
template<class T>
virtual qpp::NoiseBase< T >::~NoiseBase () [virtual], [default]
```

Default virtual destructor.

#### 7.43.4 Member Function Documentation

## 7.43.4.1 compute\_probs\_()

Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

## **Parameters**

state	State vector or density matrix
target	Qudit indexes where the noise is applied

## 7.43.4.2 compute\_state\_()

Compute the resulting state after the noise was applied.

#### **Parameters**

state	State vector or density matrix
target	Qudit indexes where the noise is applied

## Returns

Resulting state after the noise was applied

## 7.43.4.3 get\_d()

```
template<class T>
idx qpp::NoiseBase< T >::get_d ( ) const [inline], [noexcept]
```

Qudit dimension.

## Returns

Qudit dimension

# 7.43.4.4 get\_Ks()

```
template<class T>
std::vector<cmat> qpp::NoiseBase< T >::get_Ks () const [inline]
```

Vector of noise operators.

## Returns

Vector of noise operators

```
7.43.4.5 get_last_idx()
```

```
template<class T>
idx qpp::NoiseBase< T >::get_last_idx ( ) const [inline]
```

Index of the last occurring noise element.

#### Returns

Index of the last occurring noise element

```
7.43.4.6 get_last_K()
```

```
template<class T>
cmat qpp::NoiseBase< T >::get_last_K ( ) const [inline]
```

Last occurring noise element.

#### Returns

Last occurring noise element

## 7.43.4.7 get\_last\_p()

```
template<class T>
double qpp::NoiseBase< T >::get_last_p ( ) const [inline]
```

Probability of the last occurring noise element.

#### Returns

Probability of the last occurring noise element

## 7.43.4.8 get\_probs()

```
template<class T>
std::vector<double> qpp::NoiseBase< T >::get_probs ( ) const [inline]
```

Vector of probabilities corresponding to each noise operator.

## Returns

Probability vector

## **7.43.4.9** operator()() [1/3]

Function invocation operator, applies the underlying noise model on the state vector or density matrix *state*.

#### **Parameters**

tate State vector or density matrix
-------------------------------------

## Returns

Resulting state vector or density matrix

# 

Function invocation operator, applies the underlying noise model on qudit *target* of the multi-partite state vector or density matrix *state*.

#### **Parameters**

state	Multi-partite state vector or density matrix
target	Qudit index where the noise is applied

#### Returns

Resulting state vector or density matrix

Function invocation operator, applies the underlying correlated noise model on qudits specified by *target* of the multi-partite state vector or density matrix *state*.

const std::vector< idx > & target) const [inline], [virtual]

#### **Parameters**

state	Multi-partite state vector or density matrix
target	Qudit indexes where the correlated noise is applied

#### Returns

Resulting state vector or density matrix

#### 7.43.5 Member Data Documentation

```
7.43.5.1 d_
template<class T>
idx qpp::NoiseBase< T >::d_ {} [mutable], [protected]
qudit dimension
7.43.5.2 generated_
template<class T>
bool qpp::NoiseBase< T >::generated_ {false} [mutable], [protected]
invoked, or if the noise is state-independent
set to true after compute_state_() is
7.43.5.3 i_
template<class T>
idx qpp::NoiseBase< T >::i_ {} [mutable], [protected]
index of the last occurring noise element
7.43.5.4 Ks_
{\tt template}{<}{\tt class} \ {\tt T}{>}
```

const std::vector<cmat> qpp::NoiseBase< T >::Ks\_ [protected]

Kraus operators.

#### 7.43.5.5 probs\_

probabilities

```
template<class T>
std::vector<double> qpp::NoiseBase< T >::probs_ [mutable], [protected]
```

The documentation for this class was generated from the following file:

· classes/noise.h

# 7.44 qpp::NoiseType Class Reference

Contains template tags used to specify the noise type.

```
#include <classes/noise.h>
```

#### Classes

· class StateDependent

Template tag, used whenever the noise is state-dependent.

· class StateIndependent

Template tag, used whenever the noise is state-independent.

# 7.44.1 Detailed Description

Contains template tags used to specify the noise type.

The documentation for this class was generated from the following file:


• classes/noise.h

# 7.45 qpp::exception::NotBipartite Class Reference


Not bi-partite exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::NotBipartite:



Collaboration diagram for qpp::exception::NotBipartite:



# **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

# 7.45.1 Detailed Description

Not bi-partite exception.

std::vector<idx> of dimensions has size different from 2

# 7.45.2 Member Function Documentation

## 7.45.2.1 description()

```
std::string qpp::exception::NotBipartite::description ( ) const [inline], [override], [virtual]
```

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

#### 7.45.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.46 qpp::exception::NotImplemented Class Reference


Code not yet implemented.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotImplemented:



Collaboration diagram for qpp::exception::NotImplemented:



# **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

# 7.46.1 Detailed Description

Code not yet implemented.

## 7.46.2 Member Function Documentation

## 7.46.2.1 description()

std::string qpp::exception::NotImplemented::description ( ) const [inline], [override], [virtual]

Exception description.

## Returns

**Exception** description

Implements qpp::exception::Exception.

# 7.46.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

# **Parameters**

where	Text representing where the exception occurred
VVIICIC	TOXI TODICOCITIING WINCIC LITE CACEDITOR OCCURRED

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.47 qpp::exception::NotQubitCvector Class Reference


Column vector is not 2 x 1 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitCvector:



Collaboration diagram for qpp::exception::NotQubitCvector:



# **Public Member Functions**

Exception description.

Exception (const std::string &where)

Constructs an exception.

# 7.47.1 Detailed Description

Column vector is not 2 x 1 exception.

Eigen::Matrix is not 2 x 1

# 7.47.2 Member Function Documentation

## 7.47.2.1 description()

```
std::string qpp::exception::NotQubitCvector::description ( ) const [inline], [override],
[virtual]
```

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

## 7.47.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred	
-------	--	--

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.48 qpp::exception::NotQubitMatrix Class Reference


Matrix is not 2 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitMatrix:



Collaboration diagram for qpp::exception::NotQubitMatrix:



# **Public Member Functions**

Exception description.

Exception (const std::string &where)

Constructs an exception.

# 7.48.1 Detailed Description

Matrix is not 2 x 2 exception.

Eigen::Matrix is not 2 x 2

# 7.48.2 Member Function Documentation

## 7.48.2.1 description()

std::string qpp::exception::NotQubitMatrix::description ( ) const [inline], [override], [virtual]

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

# 7.48.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

## **Parameters**

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.49 qpp::exception::NotQubitRvector Class Reference


Row vector is not 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitRvector:



Collaboration diagram for qpp::exception::NotQubitRvector:



# **Public Member Functions**

Exception description.

Exception (const std::string &where)

Constructs an exception.

# 7.49.1 Detailed Description

Row vector is not 1 x 2 exception.

Eigen::Matrix is not 1 x 2

# 7.49.2 Member Function Documentation

## 7.49.2.1 description()

```
std::string qpp::exception::NotQubitRvector::description ( ) const [inline], [override],
[virtual]
```

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

## 7.49.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where Text representing where the exception occurred
--

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.50 qpp::exception::NotQubitSubsys Class Reference


Subsystems are not qubits exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitSubsys:



Collaboration diagram for qpp::exception::NotQubitSubsys:



# **Public Member Functions**

Exception description.

Exception (const std::string &where)

Constructs an exception.

# 7.50.1 Detailed Description

Subsystems are not qubits exception.

Subsystems are not 2-dimensional (qubits)

# 7.50.2 Member Function Documentation

## 7.50.2.1 description()

std::string qpp::exception::NotQubitSubsys::description ( ) const [inline], [override], [virtual]

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

# 7.50.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

# Parameters

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.51 qpp::exception::NotQubitVector Class Reference


Vector is not 2 x 1 nor 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitVector:



Collaboration diagram for qpp::exception::NotQubitVector:



# **Public Member Functions**

• std::string description () const override

Exception description.

Exception (const std::string &where)

Constructs an exception.

# 7.51.1 Detailed Description

Vector is not 2 x 1 nor 1 x 2 exception.

Eigen::Matrix is not 2 x 1 nor 1 x 2

# 7.51.2 Member Function Documentation

## 7.51.2.1 description()

std::string qpp::exception::NotQubitVector::description ( ) const [inline], [override], [virtual]

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

# 7.51.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

# **Parameters**

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.52 qpp::exception::OutOfRange Class Reference


Argument out of range exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::OutOfRange:



Collaboration diagram for qpp::exception::OutOfRange:



# **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

# 7.52.1 Detailed Description

Argument out of range exception.

Argument out of range

# 7.52.2 Member Function Documentation

## 7.52.2.1 description()

```
std::string qpp::exception::OutOfRange::description ( ) const [inline], [override], [virtual]
```

Exception description.

## Returns

**Exception** description

Implements qpp::exception::Exception.

# 7.52.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

# Parameters

where Text representing where the exception of	rred
--	------

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.53 qpp::exception::PermInvalid Class Reference


Invalid permutation exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermInvalid:



Collaboration diagram for qpp::exception::PermInvalid:



# **Public Member Functions**

• std::string description () const override

Exception description.

Exception (const std::string &where)

Constructs an exception.

# 7.53.1 Detailed Description

Invalid permutation exception.

std::vector<idx> does note represent a valid permutation

# 7.53.2 Member Function Documentation

## 7.53.2.1 description()

```
std::string qpp::exception::PermInvalid::description ( ) const [inline], [override], [virtual]
```

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

# 7.53.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

# **Parameters**

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.54 qpp::exception::PermMismatchDims Class Reference


Permutation mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermMismatchDims:



Collaboration diagram for qpp::exception::PermMismatchDims:



# **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

# 7.54.1 Detailed Description

Permutation mismatch dimensions exception.

Size of the std::vector<idx> representing the permutation is different from the size of the std::vector<idx> of dimensions

# 7.54.2 Member Function Documentation

# 7.54.2.1 description()

```
std::string qpp::exception::PermMismatchDims::description ( ) const [inline], [override],
[virtual]
```

Exception description.

## Returns

**Exception** description

Implements qpp::exception::Exception.

# 7.54.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

	l <del>_</del>
whore	Layt representing where the exception occurred
WITCIC	Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.55 qpp::QCircuit Class Reference


Quantum circuit description.

#include <classes/circuits/circuits.h>

Inheritance diagram for qpp::QCircuit:



Collaboration diagram for qpp::QCircuit:



## **Classes**

• struct GateStep

One step consisting only of gates/operators in the circuit.

· class iterator

Quantum circuit bound-checking (safe) iterator.

struct MeasureStep

One step consisting only of measurements in the circuit.

## **Public Types**

enum GateType {
 GateType::NONE, GateType::SINGLE, GateType::TWO, GateType::THREE,
 GateType::CUSTOM, GateType::FAN, GateType::SINGLE\_CTRL\_SINGLE\_TARGET, GateType::SINGLE\_CTRL\_MULTIPLE\_
 GateType::MULTIPLE\_CTRL\_SINGLE\_TARGET, GateType::MULTIPLE\_TARGET,
 GateType::CUSTOM\_CTRL, GateType::SINGLE\_cCTRL\_SINGLE\_TARGET,
 GateType::SINGLE\_cCTRL\_MULTIPLE\_TARGET, GateType::MULTIPLE\_cCTRL\_SINGLE\_TARGET,
 GateType::MULTIPLE\_cCTRL\_MULTIPLE\_TARGET, GateType::CUSTOM\_cCTRL}
 Type of gate being executed in a gate step.
 enum MeasureType {
 MeasureType::NONE, MeasureType::MEASURE\_Z, MeasureType::MEASURE\_Z\_MANY, MeasureType::MEASURE\_V, MeasureType::MEASURE\_V\_MANY}

Type of measurement being executed in a measurement step.

enum StepType { StepType::NONE, StepType::GATE, StepType::MEASUREMENT, StepType::NOP }

Types of each step in the quantum circuit.

using const iterator = iterator

both iterators are const\_iterators

#### **Public Member Functions**

• iterator begin ()

Iterator to the first element.

· const iterator begin () const noexcept

Constant iterator to the first element.

· const iterator cbegin () const noexcept

Constant iterator to the first element.

• iterator end ()

Iterator to the next to the last element.

const\_iterator end () const noexcept

Constant iterator to the next to the last element.

· const iterator cend () const noexcept

Constant iterator to the next to the last element.

QCircuit (idx nq, idx nc=0, idx d=2, std::string name={})

Constructs a quantum circuit.

virtual ~QCircuit ()=default

Default virtual destructor.

• idx get\_nq () const noexcept

Total number of qudits in the circuit.

• idx get\_nc () const noexcept

Total number of classical dits in the circuit.

• idx get\_d () const noexcept

Dimension of the comprising qudits.

• std::string get\_name () const

Quantum circuit name.

· idx get measured (idx i) const

Check whether qudit i was already measured.

std::vector< idx > get measured () const

Vector of already measured qudit indexes.

std::vector< idx > get\_non\_measured () const

Vector of non-measured qudit indexes.

idx get\_gate\_count (const std::string &name={}) const

Quantum circuit gate count.

• idx get\_depth (const std::string &name={}) const

Quantum circuit depth.

idx get\_measurement\_count () const noexcept

Quantum circuit total measurement count.

• idx get measurement count (const std::string &name) const

Quantum circuit measurement count.

idx get\_step\_count () const noexcept

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

· idx get nop count () const

No-op count.

QCircuit & add\_qudit (idx n=1, idx i=-1)

Adds n additional qudits before qudit i (by default adds them at the end)

QCircuit & add\_dit (idx n=1, idx i=-1)

Adds n additional classical dits before dit i (by default adds them at the end)

QCircuit & gate (const cmat &U, idx i, std::string name={})

Applies the single qudit gate U on single qudit i.

QCircuit & gate (const cmat &U, idx i, idx j, std::string name={})

Applies the two qudit gate U on qudits i and j.

• QCircuit & gate (const cmat &U, idx i, idx j, idx k, std::string name={})

Applies the three qudit gate U on qudits i, j and k.

QCircuit & gate fan (const cmat &U, const std::vector < idx > &target, std::string name={})

Applies the single qudit gate U on every qudit listed in target.

• QCircuit & gate\_fan (const cmat &U, const std::initializer\_list< idx > &target, std::string name={})

Applies the single qudit gate U on every qudit listed in target.

QCircuit & gate\_fan (const cmat &U, std::string name={})

Applies the single qudit gate U on every remaining non-measured qudit.

QCircuit & gate\_custom (const cmat &U, const std::vector< idx > &target, std::string name={})

Jointly applies the custom multiple qudit gate U on the qudit indexes specified by target.

QCircuit & QFT (const std::vector < idx > &target, bool swap=true)

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & QFT (const std::initializer\_list< idx > &target, bool swap=true)

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & QFT (bool swap=true)

Applies the quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

QCircuit & TFQ (const std::vector < idx > &target, bool swap QPP\_UNUSED\_=true)

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & TFQ (const std::initializer\_list< idx > &target, bool swap=true)

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & TFQ (bool swap=true)

Applies the inverse quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

QCircuit & CTRL (const cmat &U, idx ctrl, idx target, std::string name={})

Applies the single qudit controlled gate U with control qudit ctrl and target qudit target.

QCircuit & CTRL (const cmat &U, idx ctrl, const std::vector < idx > &target, std::string name={})

Applies the single qudit controlled gate U with control qudit ctrl on every qudit listed in target.

QCircuit & CTRL (const cmat &U, const std::vector < idx > &ctrl, idx target, std::string name={})

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on the target qudit target.

QCircuit & CTRL (const cmat &U, const std::vector < idx > &ctrl, const std::vector < idx > &target, std::string name={})

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on every qudit listed in target.

QCircuit & CTRL\_custom (const cmat &U, const std::vector < idx > &ctrl, const std::vector < idx > &target, std::string name={})

Jointly applies the custom multiple-qudit controlled gate U with multiple control qudits listed in ctrl on the qudit indexes specified by target.

QCircuit & cCTRL (const cmat &U, idx ctrl\_dit, idx target, std::string name={})

Applies the single qubit controlled gate U with classical control dit ctrl and target qudit target.

QCircuit & cCTRL (const cmat &U, idx ctrl\_dit, const std::vector < idx > &target, std::string name={})

Applies the single qudit controlled gate U with classical control dit ctrl on every qudit listed in target.

QCircuit & cCTRL (const cmat &U, const std::vector < idx > &ctrl\_dits, idx target, std::string name={})

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on the target qudit target.

QCircuit & cCTRL (const cmat &U, const std::vector< idx > &ctrl\_dits, const std::vector< idx > &target, std::string name={})

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on every qudit listed in target.

QCircuit & cCTRL\_custom (const cmat &U, const std::vector< idx > &ctrl\_dits, const std::vector< idx > &target, std::string name={})

Jointly applies the custom multiple-qudit controlled gate U with multiple classical control dits listed in ctrl on the qudit indexes specified by target.

QCircuit & measureZ (idx target, idx c reg, std::string name={})

Measurement of single qudit in the computational basis (Z-basis)

QCircuit & measureZ (const std::vector < idx > &target, idx c\_reg, std::string name={})

Measurement of multiple qudit in the computational basis (Z-basis)

QCircuit & measureV (const cmat &V, idx target, idx c\_reg, std::string name={})

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

QCircuit & measureV (const cmat &V, const std::vector< idx > &target, idx c\_reg, std::string name={})

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

· QCircuit & nop ()

No operation (no-op)

· QCircuit & replicate (idx n)

Replicates the circuit.

QCircuit & add\_circuit (QCircuit other, bigint pos\_qudit, idx pos\_dit=-1)

Appends a quantum circuit description to the current one.

· QCircuit & kron (const QCircuit &other)

Kronecker product with another quantum circuit description.

· std::string to JSON (bool enclosed in curly brackets=true) const override

qpp::/JSON::to\_JSON() override

#### **Private Member Functions**

void add\_hash\_ (const cmat &U, std::size\_t hashU)

Adds matrix to the hash table.

• const std::vector< MeasureStep > & get\_measurements\_ () const noexcept

Vector of qpp::QCircuit::MeasureStep.

const std::vector < GateStep > & get\_gates\_ () const noexcept

Vector of qpp::QCircuit::GateStep.

const std::unordered map< std::size t, cmat > & get cmat hash tbl () const noexcept

Hash table with the matrices used in the circuit.

• std::ostream & display (std::ostream &os) const override

qpp::IDisplay::display() override

#### **Private Attributes**

```
• idx nq_
     number of qudits

    idx nc

     number of classical "dits"

    const idx d

     qudit dimension

    std::string name

     optional circuit name

    std::vector< bool > measured

     keeps track of the measured qudits
std::unordered_map< std::size_t, cmat > cmat_hash_tbl_{}{}
• std::unordered_map< std::string, idx > count_{\{}
     gate counts

    std::unordered_map< std::string, idx > measurement_count_{}{}

     measurement counts
std::vector< GateStep > gates_{}{}
std::vector< MeasureStep > measurements_{}{}
     measurements
std::vector< StepType > step_types_{}
     type of each step
```

# **Friends**

- · class QEngine
- std::ostream & operator<< (std::ostream &os, const GateType &gate\_type)

Extraction operator overload for qpp::QCircuit::GateType enum class.

• std::ostream & operator<< (std::ostream &os, const GateStep &gate\_step)

Extraction operator overload for qpp::QCircuit::GateStep class.

std::ostream & operator<< (std::ostream &os, const MeasureType &measure\_type)</li>

Extraction operator overload for qpp::QCircuit::MeasureType enum class.

std::ostream & operator<< (std::ostream &os, const MeasureStep &measure\_step)</li>

Extraction operator overload for qpp::QCircuit::MeasureStep class.

## 7.55.1 Detailed Description

Quantum circuit description.

See also

qpp::QEngine

# 7.55.2 Member Typedef Documentation

# 7.55.2.1 const\_iterator

using qpp::QCircuit::const\_iterator = iterator

both iterators are const\_iterators

# 7.55.3 Member Enumeration Documentation

# 7.55.3.1 GateType

```
enum qpp::QCircuit::GateType [strong]
```

Type of gate being executed in a gate step.

#### Enumerator

NONE	represents no gate
SINGLE	unitary gate on a single qudit
TWO	unitary gate on 2 qudits
THREE	unitary gate on 3 qudits
CUSTOM	custom gate on multiple qudits
FAN	same unitary gate on multiple qudits
SINGLE_CTRL_SINGLE_TARGET	one control and one target controlled 1 qudit unitary gate with
SINGLE_CTRL_MULTIPLE_TARGET	one control and multiple targets controlled 1 qudit unitary gate with
MULTIPLE_CTRL_SINGLE_TARGET	multiple controls and single target controlled 1 qudit unitary gate with
MULTIPLE_CTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with multiple controls and multiple targets
CUSTOM_CTRL	and multiple targets custom controlled gate with multiple controls
SINGLE_cCTRL_SINGLE_TARGET	one classical control and one target controlled 1 qudit unitary gate with
SINGLE_cCTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with one classical control and multiple targets
MULTIPLE_cCTRL_SINGLE_TARGET	controlled 1 qudit unitary gate with multiple classical controls and single target
MULTIPLE_cCTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with multiple classical controls and multiple targets
CUSTOM_cCTRL	controls and multiple targets custom controlled gate with multiple classical

# 7.55.3.2 MeasureType

enum qpp::QCircuit::MeasureType [strong]

Type of measurement being executed in a measurement step.

#### Enumerator

NONE	represents no measurement
MEASURE_Z	Z measurement of single qudit.
MEASURE_Z_MANY	Z measurement of multiple qudit.
MEASURE_V	measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix ${\it V}$
MEASURE_V_MANY	joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified

# 7.55.3.3 StepType

```
enum qpp::QCircuit::StepType [strong]
```

Types of each step in the quantum circuit.

## Enumerator

NONE	represents no step
GATE	quantum gate(s)
MEASUREMENT	measurement
NOP	no-op

# 7.55.4 Constructor & Destructor Documentation

# 7.55.4.1 QCircuit()

```
qpp::QCircuit::QCircuit (
    idx nq,
    idx nc = 0,
    idx d = 2,
    std::string name = {} ) [inline], [explicit]
```

Constructs a quantum circuit.

### Note

The measurement results can only be stored in the classical dits of which number is specified by *nc* 

## **Parameters**

nq	Number of qbits	
nc	Number of classical dits (optional)	
d	Subsystem dimensions (optional, default is qubit, i.e. $d = 2$ )	
aளவ்ளை by கிழ்துள் name (optional)		

#### 7.55.4.2 ~QCircuit()

```
virtual qpp::QCircuit::~QCircuit ( ) [virtual], [default]
```

Default virtual destructor.

#### 7.55.5 Member Function Documentation

#### 7.55.5.1 add\_circuit()

Appends a quantum circuit description to the current one.

#### Note

If qudit indexes of the added quantum circuit description do not totally overlap with the indexes of the current quantum circuit description, then the required number of additional qudits are automatically added to the current quantum circuit description

#### **Parameters**

other	Quantum circuit description
pos_qudit	The index of the first qudit of <i>other</i> relative to the index of the first qudit of the current quantum circuit description, with the rest following in order. If negative or greater than the total number of qudits of the current quantum circuit description, the required number of additional qudits are automatically added to the current quantum circuit description.
pos_dit	The first classical dit of <i>other</i> is inserted before the <i>pos_dit</i> classical dit index of the current quantum circuit description (in the classical dits array), the rest following in order. By default, insertion is performed at the end.

# Returns

Reference to the current instance

## 7.55.5.2 add\_dit()

```
QCircuit& qpp::QCircuit::add_dit (  idx \ n = 1, \\  idx \ i = -1 \ ) \quad [inline]
```

Adds *n* additional classical dits before dit *i* (by default adds them at the end)

#### Note

Classical dits with indexes greater or equal than the newly inserted ones have their indexes automatically incremented

#### **Parameters**

n	Number of classical dits
i	Classical dit index

#### Returns

Reference to the current instance

## 7.55.5.3 add\_hash\_()

Adds matrix to the hash table.

Note

Throws if a hash collision is detected., i.e., if two different matrices have the same hash

# Parameters

U	Complex matrix
hashU	Hash value of U

## 7.55.5.4 add\_qudit()

```
QCircuit& qpp::QCircuit::add_qudit (  \mbox{idx } n = 1, \\ \mbox{idx } i = -1 \mbox{) [inline]}
```

Adds n additional qudits before qudit i (by default adds them at the end)

Note

Qudits with indexes greater or equal than the newly inserted ones have their indexes automatically incremented

#### **Parameters**

n	Number of qudits
i	Qudit index

## Returns

Reference to the current instance

```
7.55.5.5 begin() [1/2]
iterator qpp::QCircuit::begin ( ) [inline]
```

Iterator to the first element.

Returns

Iterator to the first element

```
7.55.5.6 begin() [2/2]
const_iterator qpp::QCircuit::begin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

```
7.55.5.7 cbegin()
const_iterator qpp::QCircuit::cbegin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

Applies the single qubit controlled gate *U* with classical control dit *ctrl* and target qudit *target*.

#### **Parameters**

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit index
name	Optional gate name

#### Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with classical control dit *ctrl* on every qudit listed in *target*.

#### **Parameters**

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit indexes; the gate $U$ is applied on every one of them depending on the values of the
	classical control dits
name	Optional gate name

#### Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the target qudit *target*.

#### **Parameters**

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit index
name	Optional gate name

#### Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on every qudit listed in *target*.

## **Parameters**

U	Single qudit quantum gate	
ctrl_dits	Classical control dits indexes	
target	Target qudit indexes; the gate $U$ is applied on every one of them depending on the values of the	
	classical control dits	
name	Optional gate name	

#### Returns

Reference to the current instance

# 7.55.5.12 cCTRL\_custom()

Jointly applies the custom multiple-qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the qudit indexes specified by *target*.

#### **Parameters**

U	Multiple-qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit indexes where the gate $U$ is applied depending on the values of the classical control dits
name	Optional gate name

#### Returns

Reference to the current instance

# 7.55.5.13 cend()

```
const_iterator qpp::QCircuit::cend ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

#### Returns

Constant iterator to the next to the last element

```
7.55.5.14 CTRL() [1/4]
```

Applies the single qudit controlled gate *U* with control qudit *ctrl* and target qudit *target*.

## **Parameters**

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit index
name	Optional gate name

# Returns

Reference to the current instance

```
7.55.5.15 CTRL() [2/4]
```

Applies the single qudit controlled gate *U* with control qudit *ctrl* on every qudit listed in *target*.

#### **Parameters**

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit indexes; the gate $U$ is applied on every one of them depending on the values of the control qudits
name	Optional gate name

#### Returns

Reference to the current instance

```
7.55.5.16 CTRL() [3/4]
```

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the target qudit *target*.

#### **Parameters**

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit index
name	Optional gate name

## Returns

Reference to the current instance

```
7.55.5.17 CTRL() [4/4]
```

```
QCircuit& qpp::QCircuit::CTRL (
const cmat & U,
```

```
const std::vector< idx > & ctrl,
const std::vector< idx > & target,
std::string name = {} ) [inline]
```

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on every qudit listed in *target*.

#### **Parameters**

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes; the gate $U$ is applied on every one of them depending on the values of the control qudits
name	Optional gate name

#### Returns

Reference to the current instance

#### 7.55.5.18 CTRL\_custom()

Jointly applies the custom multiple-qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the qudit indexes specified by *target*.

# Parameters

U	Multiple-qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes where the gate $U$ is applied depending on the values of the control qudits
name	Optional gate name

#### Returns

Reference to the current instance

#### 7.55.5.19 display()

## qpp::IDisplay::display() override

Writes to the output stream a textual representation of the quantum circuit

#### **Parameters**

```
os Output stream passed by reference
```

## Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.55.5.20 end() [1/2]
iterator qpp::QCircuit::end ( ) [inline]
```

Iterator to the next to the last element.

## Returns

Iterator to the next to the last element

```
7.55.5.21 end() [2/2]
const_iterator qpp::QCircuit::end ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

## Returns

Constant iterator to the next to the last element

Applies the single qudit gate *U* on single qudit *i*.

#### **Parameters**

U	Single qudit quantum gate
i	Qudit index
name	Optional gate name

#### Returns

Reference to the current instance

Applies the two qudit gate *U* on qudits *i* and *j*.

#### **Parameters**

U	Two qudit quantum gate
i	Qudit index
j	Qudit index
name	Optional gate name

## Returns

Reference to the current instance

Applies the three qudit gate U on qudits i, j and k.

# **Parameters**

U	Three qudit quantum gate
i	Qudit index
j	Qudit index
k	Qudit index
name	Optional gate name

#### Returns

Reference to the current instance

## 7.55.5.25 gate\_custom()

Jointly applies the custom multiple qudit gate *U* on the qudit indexes specified by *target*.

## **Parameters**

U	Multiple qudit quantum gate	
target	Subsystem indexes where the gate <i>U</i> is applied	
name	Optional gate name	

#### Returns

Reference to the current instance

```
7.55.5.26 gate_fan() [1/3]
```

Applies the single qudit gate *U* on every qudit listed in *target*.

# Parameters

U	Single qudit quantum gate
target	Target qudit indexes; the gate <i>U</i> is applied on every one of them
name	Optional gate name

## Returns

Reference to the current instance

```
7.55.5.27 gate_fan() [2/3]
```

Applies the single qudit gate *U* on every qudit listed in *target*.

#### **Parameters**

U	Single qudit quantum gate	
target	Target qudit indexes; the gate $U$ is applied on every one of them	
name	Optional gate name	

#### Returns

Reference to the current instance

```
7.55.5.28 gate_fan() [3/3]
```

Applies the single qudit gate U on every remaining non-measured qudit.

#### **Parameters**

U	Single qudit quantum gate	
name	Optional gate name	

# Returns

Reference to the current instance

#### 7.55.5.29 get\_cmat\_hash\_tbl\_()

```
const std::unordered_map<std::size_t, cmat>& qpp::QCircuit::get_cmat_hash_tbl_ ( ) const
[inline], [private], [noexcept]
```

Hash table with the matrices used in the circuit.

#### Returns

Hash table with the matrices used in the circuit

```
7.55.5.30 get_d()
```

```
idx qpp::QCircuit::get_d ( ) const [inline], [noexcept]
```

Dimension of the comprising qudits.

## Returns

Qudit dimension

# 7.55.5.31 get\_depth()

Quantum circuit depth.

Note

If name is empty (default), returns the total depth of the circuit

## **Parameters**

name	Gate/measurement name (optional)
------	----------------------------------

# Returns

Gate/measurement depth

## 7.55.5.32 get\_gate\_count()

Quantum circuit gate count.

Note

If name is empty (default), returns the total gate count of the circuit

## **Parameters**

name	Gate name (optional)	e name (optional)

#### Returns

Gate count

```
7.55.5.33 get_gates_()
const std::vector<GateStep>& qpp::QCircuit::get_gates_ ( ) const [inline], [private], [noexcept]
Vector of qpp::QCircuit::GateStep.
```

## Returns

Vector of qpp::QCircuit::GateStep

```
7.55.5.34 get_measured() [1/2] idx qpp::QCircuit::get_measured ( idx i ) const [inline]
```

Check whether qudit *i* was already measured.

#### **Parameters**

i Qudit index

## Returns

True if qudit i was already measured, false othwewise

```
7.55.5.35 get_measured() [2/2]
std::vector<idx> qpp::QCircuit::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

## Returns

Vector of already measured qudit indexes

```
7.55.5.36 get_measurement_count() [1/2]
```

```
idx qpp::QCircuit::get_measurement_count ( ) const [inline], [noexcept]
```

Quantum circuit total measurement count.

Returns

Total measurement count

```
7.55.5.37 get_measurement_count() [2/2]
```

Quantum circuit measurement count.

#### **Parameters**

name	Measurement name
------	------------------

Returns

Measurement count

```
7.55.5.38 get_measurements_()
```

```
\verb|const| std::vector<| MeasureStep>& qpp::QCircuit::get_measurements_ ( ) const [inline], [private], [noexcept] \\
```

Vector of qpp::QCircuit::MeasureStep.

Returns

Vector of qpp::QCircuit::MeasureStep

```
7.55.5.39 get_name()
```

```
std::string qpp::QCircuit::get_name ( ) const [inline]
```

Quantum circuit name.

Returns

Quantum circuit name

```
7.55.5.40 get_nc()
```

```
idx qpp::QCircuit::get_nc ( ) const [inline], [noexcept]
```

Total number of classical dits in the circuit.

#### Returns

Total number of classical dits

```
7.55.5.41 get_non_measured()
```

```
std::vector<idx> qpp::QCircuit::get_non_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

#### Returns

Vector of non-measured qudit indexes

# 7.55.5.42 get\_nop\_count()

```
idx qpp::QCircuit::get_nop_count ( ) const [inline]
```

No-op count.

## Returns

No-op count

#### 7.55.5.43 get\_nq()

```
idx qpp::QCircuit::get_nq ( ) const [inline], [noexcept]
```

Total number of qudits in the circuit.

#### Returns

Total number of qudits

```
7.55.5.44 get_step_count()
```

```
idx qpp::QCircuit::get_step_count ( ) const [inline], [noexcept]
```

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

# Returns

Total (gates + measurements) count

# 7.55.5.45 kron()

Kronecker product with another quantum circuit description.

#### **Parameters**

## Returns

Reference to the current instance

#### 7.55.5.46 measureV() [1/2]

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

#### **Parameters**

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V	
target	Qudit index	
c_reg	Classical register where the value of the measurement is stored	
name	Optional measurement name	

#### Returns

Reference to the current instance

# **7.55.5.47** measureV() [2/2]

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

#### **Parameters**

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V	
target	Target qudit indexes that are jointly measured	
c_reg	c_reg Classical register where the value of the measurement is stored	
name	Optional measurement name	

#### Returns

Reference to the current instance

Measurement of single qudit in the computational basis (Z-basis)

## **Parameters**

target	Qudit index
c_reg	Classical register where the value of the measurement is being stored
name	Optional measurement name, default is "mZ"

## Returns

Reference to the current instance

idx c\_reg,

7.55.5.49 measureZ() [2/2]

Measurement of multiple qudit in the computational basis (Z-basis)

std::string name = {} ) [inline]

# Parameters

target	Target qudit indexes that are measured
c_reg	Classical register where the value of the measurement is being stored, as a decimal representation of the binary string representing the measurement, with the most significant dit on the left (corresponding to the first qudit that is being measured)
name	Optional measurement name, default is "mZ"

## Returns

Reference to the current instance

```
7.55.5.50 nop()
```

```
QCircuit& qpp::QCircuit::nop ( ) [inline]
```

No operation (no-op)

Note

If the underlying step is executed on a noisy engine, then noise acts before it

#### Returns

Reference to the current instance

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

#### **Parameters**

target	target Subsystem indexes where the quantum Fourier transform is applied	
swap	Swaps the qubits at the end (true by default)	

### Returns

Reference to the current instance

bool swap = true ) [inline]

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

### **Parameters**

target	Subsystem indexes where the quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

#### Returns

Reference to the current instance

Applies the quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

#### **Parameters**

```
swap Swaps the qubits at the end (true by default)
```

#### Returns

Reference to the current instance

### 7.55.5.54 replicate()

Replicates the circuit.

Note

The circuit should not contain any measurements when invoking this member function

### **Parameters**

```
n Number of repetitions. If n == 1, returns the original circuit.
```

### Returns

Reference to the current instance

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by <i>target</i> .

#### **Parameters**

target	Subsystem indexes where the inverse quantum Fourier transform is applied	
swap	Swaps the qubits at the end (true by default)	

#### Returns

Reference to the current instance

bool swap = true ) [inline]

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

#### **Parameters**

target	Subsystem indexes where the inverse quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

#### Returns

Reference to the current instance

Applies the inverse quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

# **Parameters**

swap	Swaps the qubits at the end (true by default)
------	---

### Returns

Reference to the current instance

```
7.55.5.58 to_JSON()
```

qpp::IJSON::to\_JSON() override

Displays the quantum circuit in JSON format

#### **Parameters**

-		
		l
	analaced in surly breekets	If true, encloses the result in curly brackets
	encioseo in cunv biackeis	i il liue, encloses me resuli in cunv prackeis

#### Returns

String containing the JSON representation of the quantum circuit

Implements qpp::IJSON.

#### 7.55.6 Friends And Related Function Documentation

Extraction operator overload for qpp::QCircuit::GateType enum class.

#### **Parameters**

os	Output stream
gate_type	qpp::QCircuit::GateType enum class

#### Returns

Output stream

Extraction operator overload for qpp::QCircuit::GateStep class.

#### **Parameters**

os	Output stream
gate_step	qpp::QCircuit::GateStep class

#### Returns

Output stream

Extraction operator overload for <a href="mailto:qpp::QCircuit::MeasureType">qpp::QCircuit::MeasureType</a> enum class.

#### **Parameters**

os	Output stream
measure_type	qpp::QCircuit::MeasureType enum class

#### Returns

Output stream

Extraction operator overload for qpp::QCircuit::MeasureStep class.

#### **Parameters**

os	Output stream
measure_step	qpp::QCircuit::MeasureStep enum class

#### Returns

Output stream

```
7.55.6.5 QEngine
```

```
friend class QEngine [friend]
```

#### 7.55.7 Member Data Documentation

```
7.55.7.1 cmat_hash_tbl_
std::unordered_map<std::size_t, cmat> qpp::QCircuit::cmat_hash_tbl_ {} [private]
hash table with the matrices used in the circuit, with [Key = std::size_t, Value = cmat]
7.55.7.2 count_
std::unordered_map<std::string, idx> qpp::QCircuit::count_ {} [private]
gate counts
7.55.7.3 d_
const idx qpp::QCircuit::d_ [private]
qudit dimension
7.55.7.4 gates_
std::vector<GateStep> qpp::QCircuit::gates_ {} [private]
gates
7.55.7.5 measured_
std::vector<bool> qpp::QCircuit::measured_ [private]
keeps track of the measured qudits
```

```
7.55.7.6 measurement_count_
std::unordered_map<std::string, idx> qpp::QCircuit::measurement_count_ {} [private]
measurement counts
7.55.7.7 measurements_
std::vector<MeasureStep> qpp::QCircuit::measurements_ {} [private]
measurements
7.55.7.8 name_
std::string qpp::QCircuit::name_ [private]
optional circuit name
7.55.7.9 nc_
idx qpp::QCircuit::nc_ [private]
number of classical "dits"
7.55.7.10 nq_
idx qpp::QCircuit::nq_ [private]
number of qudits
7.55.7.11 step_types_
std::vector<StepType> qpp::QCircuit::step_types_ {} [private]
type of each step
```

• classes/circuits/circuits.h


The documentation for this class was generated from the following file:

# 7.56 qpp::QEngine Class Reference


Quantum circuit engine, executes qpp::QCircuit.

#include <classes/circuits/engines.h>

Inheritance diagram for qpp::QEngine:



### Collaboration diagram for qpp::QEngine:



#### **Public Member Functions**

• QEngine (const QCircuit &qc)

Constructs a quantum engine out of a quantum circuit.

• QEngine (const QEngine &)=default

Default copy constructor.

• QEngine & operator= (const QEngine &)=default

Default copy assignment operator.

• QEngine (QCircuit &&)=delete

Disables rvalue QCircuit.

virtual ~QEngine ()=default

Default virtual destructor.

· ket get\_psi () const

Underlying quantum state.

std::vector< idx > get\_dits () const

Vector with the values of the underlying classical dits.

• idx get\_dit (idx i) const

Value of the classical dit at position i.

std::vector< double > get\_probs () const

Vector of underlying measurement outcome probabilities.

• bool get\_measured (idx i) const

Check whether qudit i was already measured.

std::vector< idx > get\_measured () const

Vector of already measured qudit indexes.

std::vector< idx > get\_non\_measured () const

Vector of non-measured gudit indexes.

const QCircuit & get\_circuit () const noexcept

Quantum circuit.

const std::map< std::string, idx, internal::EqualSameSizeStringDits > & get\_stats () const

Measurement statistics for multiple runs.

QEngine & set\_dit (idx i, idx value)

Sets the classical dit at position i.

QEngine & set\_psi (const ket &psi)

Sets the underlying quantum state to psi.

QEngine & reset\_stats ()

Resets the collected measurement statistics hash table.

void reset (bool clear\_stats=true)

Resets the engine.

virtual void execute (const QCircuit::iterator::value\_type &elem)

Executes one step in the quantum circuit.

• void execute (const QCircuit::iterator &it)

Executes one step in the quantum circuit.

void execute (idx reps=1, bool clear\_stats=true)

Executes the entire quantum circuit.

std::string to\_JSON (bool enclosed\_in\_curly\_brackets=true) const override

qpp::/JSON::to\_JSON() override

#### **Protected Member Functions**

• void set measured (idx i)

Marks qudit i as measured then re-label accordingly the remaining non-measured qudits.

std::vector< idx > get\_relative\_pos\_ (std::vector< idx > v)

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

#### **Protected Attributes**

#### **Private Member Functions**

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display() override*

### 7.56.1 Detailed Description

Quantum circuit engine, executes qpp::QCircuit.

See also

qpp::QCircuit

#### 7.56.2 Constructor & Destructor Documentation

Constructs a quantum engine out of a quantum circuit.

Note

The quantum circuit must be an Ivalue

See also

```
qpp::QEngine(QCircuit&&)
```

Note

The initial underlying quantum state is set to  $|0\rangle^{\otimes n}$ 

#### **Parameters**

```
qc Quantum circuit
```

Default copy constructor.

Disables rvalue QCircuit.

```
7.56.2.4 \sim QEngine()
```

```
\label{eq:condition} \mbox{virtual qpp::QEngine::} \sim \mbox{QEngine ( ) [virtual], [default]}
```

Default virtual destructor.

### 7.56.3 Member Function Documentation

```
7.56.3.1 display()
```

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the state of the engine

#### **Parameters**

os Output stream passed by reference

#### Returns

Reference to the output stream

Implements qpp::IDisplay.

Executes one step in the quantum circuit.

#### **Parameters**

```
elem Step to be executed
```

Reimplemented in qpp::QNoisyEngine < NoiseModel >.

Executes one step in the quantum circuit.

### **Parameters**

```
it Iterator to the step to be executed
```

```
7.56.3.4 execute() [3/3]

void qpp::QEngine::execute (
        idx reps = 1,
        bool clear_stats = true ) [inline]
```

Executes the entire quantum circuit.

### **Parameters**

reps	Number of repetitions
clear_stats	Resets the collected measurement statistics hash table before the run

```
7.56.3.5 get_circuit()
```

```
const QCircuit& qpp::QEngine::get_circuit ( ) const [inline], [noexcept]
```

Quantum circuit.

Returns

Underlying quantum circuit

```
7.56.3.6 get_dit()
```

```
idx qpp::QEngine::get_dit (
         idx i ) const [inline]
```

Value of the classical dit at position i.

#### **Parameters**

```
i Classical dit index
```

### Returns

Value of the classical dit at position i

```
7.56.3.7 get_dits()
```

```
std::vector<idx> qpp::QEngine::get_dits ( ) const [inline]
```

Vector with the values of the underlying classical dits.

Returns

Vector of underlying classical dits

```
7.56.3.8 get_measured() [1/2]
```

```
bool qpp::QEngine::get_measured (
          idx i ) const [inline]
```

Check whether qudit *i* was already measured.

#### **Parameters**

i Qudit index

#### Returns

True if qudit i was already measured, false othwewise

```
7.56.3.9 get_measured() [2/2]
std::vector<idx> qpp::QEngine::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

#### Returns

Vector of already measured qudit indexes

#### 7.56.3.10 get\_non\_measured()

```
std::vector<idx> qpp::QEngine::get_non_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

#### Returns

Vector of non-measured qudit indexes

```
7.56.3.11 get_probs()
```

```
std::vector<double> qpp::QEngine::get_probs ( ) const [inline]
```

Vector of underlying measurement outcome probabilities.

Those should be interpreted as conditional probabilities based on the temporal order of the measurements, i.e. if we measure qubit 0, then measure qubit 1, and finally qubit 2, the resulting vector of outcome probabilities probs[2] should be interpreted as the conditional probability of qubit 2 having the outcome it had given that qubit 1 and qubit 0 had their given outcomes, respectively. As an example, if we measure the qubit 0 followed by the qubit 1 of a maximally entangled state  $(|00\rangle+|11\rangle)/\sqrt{2}$ , then the vector of outcome probabilities will be [0.5, 1].

#### Note

The probability vector has the same length as the vector of classical dits. If the measurement result is stored at the index  $c\_reg$ , then the outcome probability is automatically stored at the same index  $c\_reg$  in the probability vector.

#### Returns

Vector of underlying measurement outcome probabilities

#### 7.56.3.12 get\_psi()

```
ket qpp::QEngine::get_psi ( ) const [inline]
```

Underlying quantum state.

#### Returns

Underlying quantum state

#### 7.56.3.13 get\_relative\_pos\_()

```
\label{eq:condition} $$ std::vector < idx > qpp::QEngine::get_relative_pos_ ( \\ std::vector < idx > v ) [inline], [protected] $$
```

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

#### **Parameters**



#### Returns

Vector of qudit indexes

#### 7.56.3.14 get\_stats()

```
const std::map<std::string, idx, internal::EqualSameSizeStringDits>& qpp::QEngine::get_stats (
) const [inline]
```

Measurement statistics for multiple runs.

#### Returns

Hash table with collected measurement statistics for multiple runs, with hash key being the string representation of the vector of measurement results and value being the number of occurrences (of the vector of measurement results), with the most significant bit located at index 0 (i.e. top/left).

#### 7.56.3.15 operator=()

Default copy assignment operator.

### Returns

Reference to the current instance

#### 7.56.3.16 reset()

```
void qpp::QEngine::reset (
          bool clear_stats = true ) [inline]
```

Resets the engine.

#### **Parameters**

clear_stats	Resets the collected measurement statistics hash table (true by default)
-------------	--

Re-initializes everything to zero and sets the initial state to  $|0\rangle^{\otimes n}$ 

#### 7.56.3.17 reset\_stats()

```
QEngine& qpp::QEngine::reset_stats ( ) [inline]
```

Resets the collected measurement statistics hash table.

#### Returns

Reference to the current instance

#### 7.56.3.18 set\_dit()

Sets the classical dit at position i.

#### **Parameters**

i	Classical dit index
value	Classical dit value

#### Returns

Reference to the current instance

### 7.56.3.19 set\_measured\_()

```
void qpp::QEngine::set_measured_ (
          idx i ) [inline], [protected]
```

Marks qudit *i* as measured then re-label accordingly the remaining non-measured qudits.

#### **Parameters**

```
i Qudit index
```

#### 7.56.3.20 set\_psi()

Sets the underlying quantum state to psi.

Note

The order is lexicographical with respect to the remaining non-measured qudits

#### **Parameters**

```
psi State vector
```

#### Returns

Reference to the current instance

# 7.56.3.21 to\_JSON()

qpp::IJSON::to\_JSON() override

Displays the state of the engine in JSON format

#### **Parameters**

```
enclosed_in_curly_brackets | If true, encloses the result in curly brackets
```

### Returns

String containing the JSON representation of the state of the engine

Implements qpp::IJSON.

## 7.56.4 Member Data Documentation

```
7.56.4.1 dits_
std::vector<idx> qpp::QEngine::dits_ [protected]
classical dits
7.56.4.2 probs_
std::vector<double> qpp::QEngine::probs_ [protected]
measurement probabilities
7.56.4.3 psi_
ket qpp::QEngine::psi_ [protected]
state vector
7.56.4.4 qc_
const QCircuit* qpp::QEngine::qc_ [protected]
pointer to constant quantum circuit
7.56.4.5 stats_
std::map<std::string, idx, internal::EqualSameSizeStringDits> qpp::QEngine::stats_ [protected]
measurement statistics for multiple runs
7.56.4.6 subsys_
std::vector<idx> qpp::QEngine::subsys_ [protected]
keeps track of the measured subsystems, re-label them after measurements
```

classes/circuits/engines.h


The documentation for this class was generated from the following file:

# 7.57 qpp::QNoisyEngine < NoiseModel > Class Template Reference


Noisy quantum circuit engine, executes qpp::QCircuit.

#include <classes/circuits/engines.h>

Inheritance diagram for qpp::QNoisyEngine < NoiseModel >:



Collaboration diagram for qpp::QNoisyEngine < NoiseModel >:



### **Public Member Functions**

- QNoisyEngine (const QCircuit &qc, const NoiseModel &noise)
  - Constructs a noisy quantum engine out of a quantum circuit.
- void execute (const QCircuit::iterator::value\_type &elem) override
   Executes one step in the quantum circuit.
- std::vector< std::vector< idx > > get noise results () const
  - Vector of noise results obtained before every step in the circuit.
- virtual void execute (const QCircuit::iterator::value\_type &elem)

Executes one step in the quantum circuit.

void execute (const QCircuit::iterator &it)

Executes one step in the quantum circuit.

• void execute (idx reps=1, bool clear\_stats=true)

Executes the entire quantum circuit.

#### **Private Attributes**

• const NoiseModel noise\_

quantum noise model

 std::vector< std::vector< idx >> noise\_results\_ noise results

## **Additional Inherited Members**

#### 7.57.1 Detailed Description

```
template<typename NoiseModel> class qpp::QNoisyEngine< NoiseModel>
```

Noisy quantum circuit engine, executes qpp::QCircuit.

See also

```
qpp::QEngine, qpp::QCircuit, qpp::NoiseBase
```

Assumes an uncorrelated noise model that is applied to each non-measured qubit before every non-measurement step in the logical circuit. To add noise before a measurement, insert a no-op via <a href="mailto:qpp::QCircuit::nop()">qpp::QCircuit::nop()</a>.

### **Template Parameters**

NoiseModel Quantum noise model, should be derived from qpp::NoiseBase

### 7.57.2 Constructor & Destructor Documentation

#### 7.57.2.1 QNoisyEngine()

Constructs a noisy quantum engine out of a quantum circuit.

#### **Parameters**

qc	Quantum circuit
noise	Quantum noise model

## 7.57.3 Member Function Documentation

```
7.57.3.1 execute() [1/4]
```

```
template<typename NoiseModel >
virtual void qpp::QEngine::execute [inline]
```

Executes one step in the quantum circuit.

#### **Parameters**

elem	Step to be executed
------	---------------------

### 7.57.3.2 execute() [2/4]

```
template<typename NoiseModel >
void qpp::QEngine::execute [inline]
```

Executes the entire quantum circuit.

#### **Parameters**

reps	Number of repetitions
clear_stats	Resets the collected measurement statistics hash table before the run

### 7.57.3.3 execute() [3/4]

```
template<typename NoiseModel >
void qpp::QEngine::execute [inline]
```

Executes one step in the quantum circuit.

### Parameters

it	Iterator to	the s	step to	be .	executed
----	-------------	-------	---------	------	----------

Executes one step in the quantum circuit.

#### **Parameters**

```
elem Step to be executed
```

Reimplemented from qpp::QEngine.

#### 7.57.3.5 get\_noise\_results()

```
template<typename NoiseModel >
std::vector<std::vector<idx> > qpp::QNoisyEngine< NoiseModel >::get_noise_results ( ) const
[inline]
```

Vector of noise results obtained before every step in the circuit.

The first vector contains the noise measurement results obtained before applying the first step in the circuit, and so on, ordered by non-measured qudits. That is, the first element in the vector corresponding to noise obtained before a given step in the circuit represents the noise result obtained on the first non-measured qudit etc.

#### Returns

Vector of noise results

### 7.57.4 Member Data Documentation

```
7.57.4.1 noise_
```

```
template<typename NoiseModel >
const NoiseModel qpp::QNoisyEngine< NoiseModel >::noise_ [private]
```

## quantum noise model

#### 7.57.4.2 noise\_results\_

noise results

```
template<typename NoiseModel >
std::vector<std::vector<idx> > qpp::QNoisyEngine< NoiseModel >::noise_results_ [private]
```

The documentation for this class was generated from the following file:


· classes/circuits/engines.h

# 7.58 qpp::QubitAmplitudeDampingNoise Class Reference


Qubit amplitude damping noise, as described in Nielsen and Chuang.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitAmplitudeDampingNoise:



Collaboration diagram for qpp::QubitAmplitudeDampingNoise:



# **Public Member Functions**

QubitAmplitudeDampingNoise (double gamma)
 Qubit amplitude damping noise constructor.

### **Additional Inherited Members**

### 7.58.1 Detailed Description

Qubit amplitude damping noise, as described in Nielsen and Chuang.

#### 7.58.2 Constructor & Destructor Documentation

#### 7.58.2.1 QubitAmplitudeDampingNoise()

Qubit amplitude damping noise constructor.

#### **Parameters**

gamma	Amplitude damping coefficient
-------	-------------------------------

The documentation for this class was generated from the following file:


• classes/noise.h

# 7.59 qpp::QubitBitFlipNoise Class Reference


Qubit bit flip noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitBitFlipNoise:



Collaboration diagram for qpp::QubitBitFlipNoise:



#### **Public Member Functions**

QubitBitFlipNoise (double p)
 Qubit bit flip noise constructor.

### **Additional Inherited Members**

## 7.59.1 Detailed Description

Qubit bit flip noise.

#### 7.59.2 Constructor & Destructor Documentation

### 7.59.2.1 QubitBitFlipNoise()

Qubit bit flip noise constructor.

#### **Parameters**

```
p Noise probability
```

The documentation for this class was generated from the following file:


• classes/noise.h

# 7.60 qpp::QubitBitPhaseFlipNoise Class Reference


Qubit bit-phase flip (dephasing) noise.

```
#include <classes/noise.h>
```

 $Inheritance\ diagram\ for\ qpp::Qubit Bit Phase Flip Noise:$ 



Collaboration diagram for qpp::QubitBitPhaseFlipNoise:



#### **Public Member Functions**

QubitBitPhaseFlipNoise (double p)
 Qubit bit-phase flip noise constructor.

### **Additional Inherited Members**

### 7.60.1 Detailed Description

Qubit bit-phase flip (dephasing) noise.

### 7.60.2 Constructor & Destructor Documentation

### 7.60.2.1 QubitBitPhaseFlipNoise()

Qubit bit-phase flip noise constructor.

### **Parameters**

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

# 7.61 qpp::QubitDepolarizingNoise Class Reference


Qubit depolarizing noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitDepolarizingNoise:



Collaboration diagram for qpp::QubitDepolarizingNoise:



## **Public Member Functions**

QubitDepolarizingNoise (double p)
 Qubit depolarizing noise constructor.

### **Additional Inherited Members**

### 7.61.1 Detailed Description

Qubit depolarizing noise.

### 7.61.2 Constructor & Destructor Documentation

#### 7.61.2.1 QubitDepolarizingNoise()

```
\label{eq:qpp::QubitDepolarizingNoise::QubitDepolarizingNoise (} \\ \text{double } p \text{ ) } \quad \text{[inline], [explicit]}
```

Qubit depolarizing noise constructor.

#### **Parameters**

p Noise probability

The documentation for this class was generated from the following file:


classes/noise.h

# 7.62 qpp::QubitPhaseDampingNoise Class Reference


Qubit phase damping noise, as described in Nielsen and Chuang.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitPhaseDampingNoise:



Collaboration diagram for qpp::QubitPhaseDampingNoise:



#### **Public Member Functions**

QubitPhaseDampingNoise (double lambda)
 Qubit phase damping noise constructor.

### **Additional Inherited Members**

### 7.62.1 Detailed Description

Qubit phase damping noise, as described in Nielsen and Chuang.

## 7.62.2 Constructor & Destructor Documentation

### 7.62.2.1 QubitPhaseDampingNoise()

Qubit phase damping noise constructor.

### **Parameters**

lambda	Phase damping coefficient

The documentation for this class was generated from the following file:


· classes/noise.h

# 7.63 qpp::QubitPhaseFlipNoise Class Reference


Qubit phase flip (dephasing) noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitPhaseFlipNoise:



Collaboration diagram for qpp::QubitPhaseFlipNoise:



## **Public Member Functions**

QubitPhaseFlipNoise (double p)
 Qubit phase flip (dephasing) noise constructor.

#### **Additional Inherited Members**

### 7.63.1 Detailed Description

Qubit phase flip (dephasing) noise.

### 7.63.2 Constructor & Destructor Documentation

#### 7.63.2.1 QubitPhaseFlipNoise()

Qubit phase flip (dephasing) noise constructor.

#### **Parameters**

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

# 7.64 qpp::exception::QuditAlreadyMeasured Class Reference


Qudit was already measured exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::QuditAlreadyMeasured:



Collaboration diagram for qpp::exception::QuditAlreadyMeasured:



### **Public Member Functions**

- std::string description () const override
  - Exception description.
- Exception (const std::string &where)

Constructs an exception.

### 7.64.1 Detailed Description

Qudit was already measured exception.

The qudit was already measured and cannot be measured again

### 7.64.2 Member Function Documentation

#### 7.64.2.1 description()

std::string qpp::exception::QuditAlreadyMeasured::description ( ) const [inline], [override],
[virtual]

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

#### 7.64.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

where Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.65 qpp::QuditDepolarizingNoise Class Reference


Qudit depolarizing noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QuditDepolarizingNoise:



Collaboration diagram for qpp::QuditDepolarizingNoise:



#### **Public Member Functions**

QuditDepolarizingNoise (double p, idx d)
 Qudit depolarizing noise constructor.

#### **Private Member Functions**

std::vector< cmat > fill\_Ks\_ (idx d) const

Fills the Kraus operator vector.

std::vector< double > fill\_probs\_ (double p, idx d) const
 Fills the probability vector.

### **Additional Inherited Members**

### 7.65.1 Detailed Description

Qudit depolarizing noise.

#### 7.65.2 Constructor & Destructor Documentation

#### 7.65.2.1 QuditDepolarizingNoise()

```
qpp::QuditDepolarizingNoise::QuditDepolarizingNoise ( double p,  idx \ d \ ) \ \ [inline], \ [explicit]
```

Qudit depolarizing noise constructor.

#### **Parameters**

р	Noise probability
d	Qudit dimension

# 7.65.3 Member Function Documentation

```
7.65.3.1 fill_Ks_()
std::vector<cmat> qpp::QuditDepolarizingNoise::fill_Ks_ (
```

idx d ) const [inline], [private]

Fills the Kraus operator vector.

#### **Parameters**

d Qudit dimension

# Returns

Vector of Kraus operators representing the depolarizing noise

```
7.65.3.2 fill_probs_()
```

Fills the probability vector.

#### **Parameters**

р	Probability
d	Qudit dimension

# Returns

Probability vector

The documentation for this class was generated from the following file:


• classes/noise.h

# 7.66 qpp::RandomDevices Class Reference


Singleton class that manages the source of randomness in the library.

#include <classes/random\_devices.h>

Inheritance diagram for qpp::RandomDevices:



Collaboration diagram for qpp::RandomDevices:



# **Public Member Functions**

• std::mt19937 & get\_prng ()

Returns a reference to the internal PRNG object.

std::istream & load (std::istream &is)

Loads the state of the PRNG from an input stream.

• std::ostream & save (std::ostream &os) const

Saves the state of the PRNG to an output stream.

#### **Private Member Functions**

• RandomDevices ()

Initializes and seeds the random number generators.

∼RandomDevices ()=default

Default destructor.

# **Private Attributes**

 std::random\_device rd\_ used to seed std::mt19937 prng\_

std::mt19937 prng\_

Mersenne twister random number generator.

#### **Friends**

class internal::Singleton < RandomDevices >

#### **Additional Inherited Members**

# 7.66.1 Detailed Description

Singleton class that manages the source of randomness in the library.

Consists of a wrapper around an std::mt19937 Mersenne twister random number generator engine and an std

∴ random\_device engine. The latter is used to seed the Mersenne twister.

# Warning

This class DOES NOT seed the standard C number generator used by Eigen::Matrix::Random(), since it is not thread safe. Do not use Eigen::Matrix::Random() or functions that depend on the C style random number engine, but use <a href="https://example.com/qpp::rand">qpp::rand()</a> instead!

#### 7.66.2 Constructor & Destructor Documentation

# 7.66.2.1 RandomDevices()

```
qpp::RandomDevices::RandomDevices ( ) [inline], [private]
```

Initializes and seeds the random number generators.

## 7.66.2.2 ~RandomDevices()

```
\verb"qpp::RandomDevices::$\sim$RandomDevices ( ) [private], [default]
```

Default destructor.

# 7.66.3 Member Function Documentation

```
7.66.3.1 get_prng()
```

```
std::mt19937& qpp::RandomDevices::get_prng ( ) [inline]
```

Returns a reference to the internal PRNG object.

#### Returns

Reference to the internal PRNG object

# 7.66.3.2 load()

```
std::istream& qpp::RandomDevices::load (  \texttt{std::istream \& } is \ ) \quad [inline]
```

Loads the state of the PRNG from an input stream.

# **Parameters**

```
is Input stream
```

#### Returns

The input stream

# 7.66.3.3 save()

Saves the state of the PRNG to an output stream.

**Parameters** 

os Output stream

Returns

The output stream

#### 7.66.4 Friends And Related Function Documentation

```
7.66.4.1 internal::Singleton < Random Devices >
```

```
friend class internal::Singleton< RandomDevices > [friend]
```

# 7.66.5 Member Data Documentation

```
7.66.5.1 prng_
```

```
std::mt19937 qpp::RandomDevices::prng_ [private]
```

Mersenne twister random number generator.

```
7.66.5.2 rd_
```

```
std::random_device qpp::RandomDevices::rd_ [private]
```

used to seed std::mt19937 prng\_

The documentation for this class was generated from the following file:

• classes/random\_devices.h

# 7.67 qpp::internal::Singleton < T > Class Template Reference

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

```
#include <internal/classes/singleton.h>
```

#### Static Public Member Functions

- static T & get\_instance () noexcept(std::is\_nothrow\_constructible < T >::value)
- static T & get\_thread\_local\_instance () noexcept(std::is\_nothrow\_constructible < T >::value)

#### **Protected Member Functions**

- Singleton () noexcept=default
- Singleton (const Singleton &)=delete
- Singleton & operator= (const Singleton &)=delete
- virtual ∼Singleton ()=default

# 7.67.1 Detailed Description

```
template<typename T>
class qpp::internal::Singleton< T>
```

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

To implement a singleton, derive your class from qpp::internal::Singleton, make qpp::internal::Singleton a friend of your class, then declare the constructor and destructor of your class as private. To get an instance, use the static member function qpp::internal::Singleton::get\_instance() (qpp::internal::Singleton::get\_thread\_local\_instance()), which returns a reference (thread\_local\_reference) to your newly created singleton (thread-safe in C++11).

#### Example:

## See also

Code of qpp::Codes, qpp::Gates, qpp::Init, qpp::RandomDevices, qpp::States or qpp.h for real world examples of usage.

# 7.67.2 Constructor & Destructor Documentation

```
7.67.2.1 Singleton() [1/2]

template<typename T>

qpp::internal::Singleton< T >::Singleton ( ) [protected], [default], [noexcept]
```

# 7.67.2.2 Singleton() [2/2] template<typename T> qpp::internal::Singleton< T >::Singleton ( const Singleton< T > & ) [protected], [delete] 7.67.2.3 $\sim$ Singleton() template<typename T> $\label{thm:prop} \mbox{virtual qpp::internal::Singleton< $T>::\sim$Singleton () [protected], [virtual], [default]$ 7.67.3 Member Function Documentation 7.67.3.1 get\_instance() template<typename T> static T& qpp::internal::Singleton< T >::get\_instance ( ) [inline], [static], [noexcept] 7.67.3.2 get\_thread\_local\_instance() template<typename T> static T& qpp::internal::Singleton< T >::get\_thread\_local\_instance ( ) [inline], [static], [noexcept] 7.67.3.3 operator=() template<typename T> Singleton& qpp::internal::Singleton< T >::operator= (

The documentation for this class was generated from the following file:

const Singleton< T > & ) [protected], [delete]


• internal/classes/singleton.h

# 7.68 qpp::exception::SizeMismatch Class Reference


Size mismatch exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SizeMismatch:



Collaboration diagram for qpp::exception::SizeMismatch:



# **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

# 7.68.1 Detailed Description

Size mismatch exception.

Sizes do not match

# 7.68.2 Member Function Documentation

#### 7.68.2.1 description()

std::string qpp::exception::SizeMismatch::description ( ) const [inline], [override], [virtual]

Exception description.

# Returns

**Exception** description

Implements qpp::exception::Exception.

# 7.68.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

# **Parameters**

<i>where</i>   Text repre	senting where the exception occurred
---------------------------	--------------------------------------

The documentation for this class was generated from the following file:

· classes/exception.h

# 7.69 qpp::NoiseType::StateDependent Class Reference

Template tag, used whenever the noise is state-dependent.

#include <classes/noise.h>

# 7.69.1 Detailed Description

Template tag, used whenever the noise is state-dependent.

The documentation for this class was generated from the following file:

· classes/noise.h

# 7.70 qpp::NoiseType::StateIndependent Class Reference

Template tag, used whenever the noise is state-independent.

#include <classes/noise.h>

# 7.70.1 Detailed Description

Template tag, used whenever the noise is state-independent.

The documentation for this class was generated from the following file:


classes/noise.h

# 7.71 qpp::States Class Reference


const Singleton class that implements most commonly used states

#include <classes/states.h>

Inheritance diagram for qpp::States:



Collaboration diagram for qpp::States:



# **Public Member Functions**

• ket mes (idx d=2) const

Maximally entangled state of 2 qudits.

• ket zero (idx n, idx d=2) const

Zero state of n qudits.

• ket one (idx n, idx d=2) const

One state of n qudits.

• ket jn (idx j, idx n, idx d=2) const

 $|j\rangle^{\otimes n}$  state of n qudits

• ket plus (idx n) const

Plus state of n qubits.

• ket minus (idx n) const

Minus state of n qubits.

#### **Public Attributes**

```
    ket x0 {ket::Zero(2)}
```

Pauli Sigma-X 0-eigenstate |+>

ket x1 {ket::Zero(2)}

Pauli Sigma-X 1-eigenstate |->

ket y0 {ket::Zero(2)}

Pauli Sigma-Y 0-eigenstate |y+>

ket y1 {ket::Zero(2)}

Pauli Sigma-Y 1-eigenstate | y->

ket z0 {ket::Zero(2)}

Pauli Sigma-Z 0-eigenstate |0>

ket z1 {ket::Zero(2)}

Pauli Sigma-Z 1-eigenstate | 1>

cmat px0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

cmat px1 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.

```
    cmat py0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 0-eigenstate |y+\rangle < y+|.

    cmat py1 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.

    cmat pz0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
• cmat pz1 {cmat::Zero(2, 2)}
      Projector onto the Pauli Sigma-Z 1-eigenstate | 1><1|.
ket b00 {ket::Zero(4)}
      Bell-00 state, as described in Nielsen and Chuang.

    ket b01 {ket::Zero(4)}

      Bell-01 state, as described in Nielsen and Chuang.

    ket b10 {ket::Zero(4)}

      Bell-10 state, as described in Nielsen and Chuang.
ket b11 {ket::Zero(4)}
      Bell-11 state, as described in Nielsen and Chuang.

    cmat pb00 {cmat::Zero(4, 4)}

      Projector onto the Bell-00 state.

    cmat pb01 {cmat::Zero(4, 4)}

      Projector onto the Bell-01 state.

    cmat pb10 {cmat::Zero(4, 4)}

      Projector onto the Bell-10 state.

    cmat pb11 {cmat::Zero(4, 4)}

      Projector onto the Bell-11 state.
ket GHZ {ket::Zero(8)}
      GHZ state.

    ket W {ket::Zero(8)}

      W state.
cmat pGHZ {cmat::Zero(8, 8)}
      Projector onto the GHZ state.
cmat pW {cmat::Zero(8, 8)}
```

#### **Private Member Functions**

- States ()
- ∼States ()=default

Default destructor.

Projector onto the W state.

# **Friends**

class internal::Singleton < const States >

#### **Additional Inherited Members**

# 7.71.1 Detailed Description

const Singleton class that implements most commonly used states

# 7.71.2 Constructor & Destructor Documentation

```
7.71.2.1 States()

qpp::States::States ( ) [inline], [private]

Initialize the states

7.71.2.2 ~States()

qpp::States::~States ( ) [private], [default]
```

Default destructor.

# 7.71.3 Member Function Documentation

# 7.71.3.1 jn()

 $|j\rangle^{\otimes n}$  state of *n* qudits

## **Parameters**

j	Non-negative integer
n	Non-negative integer
d	Subsystem dimensions

# Returns

 $|j\rangle^{\otimes n}$  state of *n* qudits

# 7.71.3.2 mes()

```
ket qpp::States::mes (
idx d = 2 ) const [inline]
```

Maximally entangled state of 2 qudits.

# **Parameters**

d Subsystem dimensions

# Returns

Maximally entangled state  $\frac{1}{\sqrt{d}} \sum_{j=0}^{d-1} |jj\rangle$  of 2 qudits

# 7.71.3.3 minus()

```
ket qpp::States::minus (
          idx n ) const [inline]
```

Minus state of n qubits.

# **Parameters**

n Non-negative integer

#### Returns

Minus state  $|-\rangle^{\otimes n}$  of n qubits

# 7.71.3.4 one()

```
ket qpp::States::one (
          idx n,
          idx d = 2) const [inline]
```

One state of *n* qudits.

## **Parameters**

n	Non-negative integer
d	Subsystem dimensions

# Returns

One state  $|1\rangle^{\otimes n}$  of n qudits

# 7.71.3.5 plus()

```
ket qpp::States::plus (
         idx n ) const [inline]
```

Plus state of *n* qubits.

# **Parameters**

```
n Non-negative integer
```

# Returns

Plus state  $|+\rangle^{\otimes n}$  of n qubits

# 7.71.3.6 zero()

```
ket qpp::States::zero (
         idx n,
         idx d = 2 ) const [inline]
```

Zero state of *n* qudits.

# **Parameters**

n	Non-negative integer
d	Subsystem dimensions

# Returns

Zero state  $|0\rangle^{\otimes n}$  of n qudits

# 7.71.4 Friends And Related Function Documentation

```
7.71.4.1 internal::Singleton < const States >
```

```
friend class internal::Singleton< const States > [friend]
```

# 7.71.5 Member Data Documentation

```
7.71.5.1 b00
```

```
ket qpp::States::b00 {ket::Zero(4)}
```

Bell-00 state, as described in Nielsen and Chuang.

```
7.71.5.2 b01
```

```
ket qpp::States::b01 {ket::Zero(4)}
```

Bell-01 state, as described in Nielsen and Chuang.

```
7.71.5.3 b10
```

```
ket qpp::States::b10 {ket::Zero(4)}
```

Bell-10 state, as described in Nielsen and Chuang.

# 7.71.5.4 b11

```
ket qpp::States::b11 {ket::Zero(4)}
```

Bell-11 state, as described in Nielsen and Chuang.

# 7.71.5.5 GHZ

```
ket qpp::States::GHZ {ket::Zero(8)}
```

GHZ state.

# 7.71.5.6 pb00

```
cmat qpp::States::pb00 {cmat::Zero(4, 4)}
```

Projector onto the Bell-00 state.

```
7.71 qpp::States Class Reference
7.71.5.7 pb01
cmat qpp::States::pb01 {cmat::Zero(4, 4)}
Projector onto the Bell-01 state.
7.71.5.8 pb10
cmat qpp::States::pb10 {cmat::Zero(4, 4)}
Projector onto the Bell-10 state.
7.71.5.9 pb11
cmat qpp::States::pb11 {cmat::Zero(4, 4)}
Projector onto the Bell-11 state.
7.71.5.10 pGHZ
cmat qpp::States::pGHZ {cmat::Zero(8, 8)}
Projector onto the GHZ state.
7.71.5.11 pW
cmat qpp::States::pW {cmat::Zero(8, 8)}
Projector onto the W state.
```

cmat qpp::States::px0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

7.71.5.12 px0

Generated by Doxygen

```
7.71.5.13 px1
cmat qpp::States::px1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.
7.71.5.14 py0
cmat qpp::States::py0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 0-eigenstate |y+>< y+|.
7.71.5.15 py1
cmat qpp::States::py1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.
7.71.5.16 pz0
cmat qpp::States::pz0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
7.71.5.17 pz1
cmat qpp::States::pz1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 1-eigenstate |1><1|.
7.71.5.18 W
ket qpp::States::W {ket::Zero(8)}
```

W state.

```
7.71.5.19 x0
ket qpp::States::x0 {ket::Zero(2)}
Pauli Sigma-X 0-eigenstate |+>
7.71.5.20 x1
ket qpp::States::x1 {ket::Zero(2)}
Pauli Sigma-X 1-eigenstate |->
7.71.5.21 y0
ket qpp::States::y0 {ket::Zero(2)}
Pauli Sigma-Y 0-eigenstate |y+>
7.71.5.22 y1
ket qpp::States::y1 {ket::Zero(2)}
Pauli Sigma-Y 1-eigenstate |y->
7.71.5.23 z0
ket qpp::States::z0 {ket::Zero(2)}
Pauli Sigma-Z 0-eigenstate |0>
7.71.5.24 z1
ket qpp::States::z1 {ket::Zero(2)}
Pauli Sigma-Z 1-eigenstate |1>
The documentation for this class was generated from the following file:
```


classes/states.h

# 7.72 qpp::exception::SubsysMismatchDims Class Reference


Subsystems mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SubsysMismatchDims:



Collaboration diagram for qpp::exception::SubsysMismatchDims:



# **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

# 7.72.1 Detailed Description

Subsystems mismatch dimensions exception.

std::vector<idx> of subsystem labels has duplicates, or has entries that are larger than the size of the std← ::vector<idx> of dimensions

## 7.72.2 Member Function Documentation

## 7.72.2.1 description()

std::string qpp::exception::SubsysMismatchDims::description ( ) const [inline], [override],
[virtual]

Exception description.

#### Returns

**Exception** description

Implements qpp::exception::Exception.

# 7.72.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


classes/exception.h

# 7.73 qpp::Timer < T, CLOCK\_T > Class Template Reference


Chronometer.

#include <classes/timer.h>

Inheritance diagram for qpp::Timer< T, CLOCK\_T >:



Collaboration diagram for qpp::Timer < T, CLOCK\_T >:



## **Public Member Functions**

• Timer () noexcept

Constructs an instance with the current time as the starting point.

• virtual  $\sim$ Timer ()=default

Default virtual destructor.

· void tic () noexcept

Resets the chronometer.

· const Timer & toc () noexcept

Stops the chronometer.

• double tics () const noexcept

Time passed in the duration specified by T.

• template<typename U = T>

U get\_duration () const noexcept

Duration specified by U.

# **Protected Attributes**

- CLOCK\_T::time\_point start\_
- CLOCK\_T::time\_point end\_

#### **Private Member Functions**

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display() override*

# 7.73.1 Detailed Description

```
template < typename\ T = std::chrono::duration < double >, typename\ CLOCK\_T = std::chrono::steady\_clock > class\ qpp::Timer < T,\ CLOCK\_T >
```

Chronometer.

#### **Template Parameters**

T	Tics duration, default is std::chrono::duration <double>, i.e. seconds in double precision</double>
CLOCK⊷	Clock's type, default is std::chrono::steady_clock, not affected by wall clock changes during runtime
_ <i>T</i>	

# 7.73.2 Constructor & Destructor Documentation

# 7.73.2.1 Timer()

```
\label{template} $$ \ensuremath{\texttt{template}}$ $$ \ensuremath{\texttt{typename T} = std::chrono::steady} $$ $$ \ensuremath{\texttt{clock}}$ $$ \ensuremath{\texttt{clock}}$ $$ \ensuremath{\texttt{qpp}::Timer}$ \ensuremath{\texttt{T}, CLOCK\_T} >::Timer () [inline], [noexcept] $$
```

Constructs an instance with the current time as the starting point.

# 7.73.2.2 $\sim$ Timer()

```
\label{template} $$ \ensuremath{\texttt{template}}$ $$ \ensuremath{\texttt{T}} = \ensuremath{\texttt{std}}$ : chrono::steady $$ \ensuremath{\texttt{clock}}$ $$ \ensuremath{\texttt{clock}}$ $$ \ensuremath{\texttt{virtual}}$ $$ \ensuremath{\texttt{qpp}}$ ::Timer < T, CLOCK_T >:: $$ \ensuremath{\texttt{Timer}}$ ( ) [virtual], [default] $$
```

Default virtual destructor.

# 7.73.3 Member Function Documentation

#### 7.73.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream the number of tics (specified by T) that passed between the instantiation/reset and invocation of <a href="mailto:qpp::Timer::toc">qpp::Timer::toc</a>()

#### **Parameters**

os Output stream passed by reference

#### Returns

Reference to the output stream

Implements qpp::IDisplay.

#### 7.73.3.2 get\_duration()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady 
_clock>
template<typename U = T>
U qpp::Timer< T, CLOCK_T >::get_duration ( ) const [inline], [noexcept]
```

Duration specified by U.

# **Template Parameters**

U Duration, default is T, which defaults to std::chrono::duration<double>, i.e. seconds in double precision

# Returns

Duration that passed between the instantiation/reset and invocation of <a href="mailto:qpp::Timer::toc">qpp::Timer::toc</a>()

#### 7.73.3.3 tic()

Resets the chronometer.

Resets the starting/ending point to the current time

#### 7.73.3.4 tics()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
double qpp::Timer< T, CLOCK_T >::tics ( ) const [inline], [noexcept]
```

Time passed in the duration specified by T.

#### Returns

Number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc()

# 7.73.3.5 toc()

```
\label{lock-type-ame} $$ $$ template<typename T = std::chrono::steady \leftarrow \_clock> $$ const Timer& qpp::Timer< T, CLOCK_T >::toc ( ) [inline], [noexcept] $$
```

Stops the chronometer.

Set the current time as the ending point

Returns

Reference to the current instance

# 7.73.4 Member Data Documentation

#### 7.73.4.1 end

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::end_ [protected]
```

7.73.4.2 start\_

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::start_ [protected]
```

The documentation for this class was generated from the following file:


· classes/timer.h

# 7.74 qpp::exception::TypeMismatch Class Reference


Type mismatch exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::TypeMismatch:



Collaboration diagram for qpp::exception::TypeMismatch:



#### **Public Member Functions**

- std::string description () const override
  - Exception description.
- Exception (const std::string &where)

Constructs an exception.

# 7.74.1 Detailed Description

Type mismatch exception.

Scalar types do not match

# 7.74.2 Member Function Documentation

# 7.74.2.1 description()

std::string qpp::exception::TypeMismatch::description ( ) const [inline], [override], [virtual]
Exception description.

## Returns

**Exception** description

Implements qpp::exception::Exception.

# 7.74.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


• classes/exception.h

# 7.75 qpp::exception::UndefinedType Class Reference


Not defined for this type exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::UndefinedType:



Collaboration diagram for qpp::exception::UndefinedType:



#### **Public Member Functions**

- std::string description () const override
  - Exception description.
- Exception (const std::string &where)

Constructs an exception.

# 7.75.1 Detailed Description

Not defined for this type exception.

Templated specialization is not defined for this type

# 7.75.2 Member Function Documentation

# 7.75.2.1 description()

std::string qpp::exception::UndefinedType::description ( ) const [inline], [override], [virtual]
Exception description.

## Returns

**Exception** description

Implements qpp::exception::Exception.

# 7.75.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


• classes/exception.h

# 7.76 qpp::exception::Unknown Class Reference


Unknown exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Unknown:



Collaboration diagram for qpp::exception::Unknown:



#### **Public Member Functions**

- std::string description () const override
  - Exception description.
- Exception (const std::string &where)

Constructs an exception.

# 7.76.1 Detailed Description

Unknown exception.

Thrown when no other exception is suitable (not recommended, it is better to define another suitable exception type)

# 7.76.2 Member Function Documentation

# 7.76.2.1 description()

std::string qpp::exception::Unknown::description ( ) const [inline], [override], [virtual]
Exception description.

## Returns

**Exception** description

Implements qpp::exception::Exception.

# 7.76.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred
-------	--


The documentation for this class was generated from the following file:

· classes/exception.h


# 7.77 qpp::QCircuit::iterator::value\_type\_ Class Reference

Value type class for qpp::QCircuit::iterator.

Inheritance diagram for qpp::QCircuit::iterator::value\_type\_:



Collaboration diagram for qpp::QCircuit::iterator::value\_type\_:



#### **Public Member Functions**

```
    value_type_ (const QCircuit *value_type_qc)
        Default value_type_ constructor.
    value_type_ (const value_type_ &)=default
        Default copy constructor.
    value_type_ & operator= (const value_type_ &)=default
        Default copy assignment operator.
```

# **Public Attributes**

```
    const QCircuit * value_type_qc_
        < non-owning pointer to the grand-parent const quantum circuit</li>
    StepType type_{StepType::NONE}
        step type
    idx ip_{static_cast<idx>(-1)}
        instruction pointer
    std::vector< GateStep >::const_iterator gates_ip_{gates instruction pointer}
    std::vector< MeasureStep >::const_iterator measurements_ip_{measurements instruction pointer}
```

#### **Private Member Functions**

# 7.77.1 Detailed Description

Value type class for qpp::QCircuit::iterator.

# 7.77.2 Constructor & Destructor Documentation

*value\_type\_qc* | Pointer to constant quantum circuit

Default copy constructor.

#### 7.77.3 Member Function Documentation

# 7.77.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream the textual representation of the iterator de-referenced element

#### **Parameters**

```
os Output stream passed by reference
```

# Returns

Reference to the output stream

Implements qpp::IDisplay.

# 7.77.3.2 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

# 7.77.4 Member Data Documentation

```
7.77.4.1 gates_ip_
std::vector<GateStep>::const_iterator qpp::QCircuit::iterator::value_type_::gates_ip_ {}
gates instruction pointer
7.77.4.2 ip_
idx qpp::QCircuit::iterator::value_type_::ip_ {static_cast<idx>(-1)}
instruction pointer
7.77.4.3 measurements_ip_
\verb|std::vector<| \texttt{MeasureStep}>::const_iterator | qpp::QCircuit::iterator::value_type_::measurements\_{\leftarrow}| to the const_iterator | to the const_itera
measurements instruction pointer
7.77.4.4 type_
StepType qpp::QCircuit::iterator::value_type_::type_ {StepType::NONE}
step type
7.77.4.5 value_type_qc_
const QCircuit* qpp::QCircuit::iterator::value_type_::value_type_qc_
 < non-owning pointer to the grand-parent const quantum circuit
The documentation for this class was generated from the following file:
```


• classes/circuits/circuits.h

# 7.78 qpp::exception::ZeroSize Class Reference


Object has zero size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::ZeroSize:



Collaboration diagram for qpp::exception::ZeroSize:



# **Public Member Functions**

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

# 7.78.1 Detailed Description

Object has zero size exception.

Zero sized object, e.g. empty Eigen::Matrix or std::vector with no elements

### 7.78.2 Member Function Documentation

### 7.78.2.1 description()

std::string qpp::exception::ZeroSize::description ( ) const [inline], [override], [virtual]

Exception description.

### Returns

**Exception** description

Implements qpp::exception::Exception.

### 7.78.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

### Parameters

<i>where</i>   Text repre	senting where the exception occurred
---------------------------	--------------------------------------

The documentation for this class was generated from the following file:

• classes/exception.h

370 Class Documentation


# **Chapter 8**

# **File Documentation**

# 8.1 classes/circuits/circuits.h File Reference

Qudit quantum circuits.

This graph shows which files directly or indirectly include this file:



# Classes

· class qpp::QCircuit

Quantum circuit description.

• struct qpp::QCircuit::GateStep

One step consisting only of gates/operators in the circuit.

• struct qpp::QCircuit::MeasureStep

One step consisting only of measurements in the circuit.

· class qpp::QCircuit::iterator

Quantum circuit bound-checking (safe) iterator.

• class qpp::QCircuit::iterator::value\_type\_

Value type class for qpp::QCircuit::iterator.

# **Namespaces**

• qpp

Quantum++ main namespace.


# 8.1.1 Detailed Description

Qudit quantum circuits.

# 8.2 classes/circuits/engines.h File Reference

Qudit quantum engines.

This graph shows which files directly or indirectly include this file:



#### Classes

• class qpp::QEngine

Quantum circuit engine, executes qpp::QCircuit.

class qpp::QNoisyEngine < NoiseModel >

Noisy quantum circuit engine, executes qpp::QCircuit.

# **Namespaces**

• qpp

Quantum++ main namespace.


# 8.2.1 Detailed Description

Qudit quantum engines.

# 8.3 classes/codes.h File Reference

Quantum error correcting codes.

This graph shows which files directly or indirectly include this file:



### Classes

• class qpp::Codes

const Singleton class that defines quantum error correcting codes

# **Namespaces**

• qpp

Quantum++ main namespace.

# 8.3.1 Detailed Description

Quantum error correcting codes.

# 8.4 classes/exception.h File Reference

Exceptions.

This graph shows which files directly or indirectly include this file:



#### **Classes**

class qpp::exception::Exception

Base class for generating Quantum++ custom exceptions.

class qpp::exception::Unknown

Unknown exception.

class qpp::exception::ZeroSize

Object has zero size exception.

class gpp::exception::MatrixNotSquare

Matrix is not square exception.

· class qpp::exception::MatrixNotCvector

Matrix is not a column vector exception.

class qpp::exception::MatrixNotRvector

Matrix is not a row vector exception.

class qpp::exception::MatrixNotVector

Matrix is not a vector exception.

class qpp::exception::MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

• class qpp::exception::MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

class qpp::exception::MatrixNotSquareNorVector

Matrix is not square nor vector exception.

class qpp::exception::MatrixMismatchSubsys

Matrix mismatch subsystems exception.

· class qpp::exception::DimsInvalid

Invalid dimension(s) exception.

· class qpp::exception::DimsNotEqual

Dimensions not equal exception.

class qpp::exception::DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

· class qpp::exception::DimsMismatchCvector

Dimension(s) mismatch column vector size exception.

class qpp::exception::DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

class qpp::exception::DimsMismatchVector

Dimension(s) mismatch vector size exception.

class qpp::exception::SubsysMismatchDims

Subsystems mismatch dimensions exception.

• class qpp::exception::PermInvalid

Invalid permutation exception.

· class qpp::exception::PermMismatchDims

Permutation mismatch dimensions exception.

class qpp::exception::NotQubitMatrix

Matrix is not 2 x 2 exception.

· class qpp::exception::NotQubitCvector

Column vector is not 2 x 1 exception.

class qpp::exception::NotQubitRvector

Row vector is not 1 x 2 exception.

class qpp::exception::NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

class qpp::exception::NotQubitSubsys

Subsystems are not qubits exception.

· class qpp::exception::NotBipartite

Not bi-partite exception.

· class qpp::exception::NoCodeword

Codeword does not exist exception.

class qpp::exception::OutOfRange

Argument out of range exception.

class qpp::exception::TypeMismatch

Type mismatch exception.

· class qpp::exception::SizeMismatch

Size mismatch exception.

class qpp::exception::UndefinedType

Not defined for this type exception.

• class qpp::exception::QuditAlreadyMeasured

Qudit was already measured exception.

class qpp::exception::Duplicates

System (e.g. std::vector) has duplicates exception.

class qpp::exception::CustomException

Custom exception.

· class qpp::exception::NotImplemented

Code not yet implemented.

· class qpp::exception::InvalidIterator

Invalid iterator.

#### **Namespaces**

• qpp

Quantum++ main namespace.

• qpp::exception

Quantum++ exception hierarchy namespace.


# 8.4.1 Detailed Description

Exceptions.

# 8.5 classes/gates.h File Reference

Quantum gates.

This graph shows which files directly or indirectly include this file:



### **Classes**

class qpp::Gates

const Singleton class that implements most commonly used gates

# **Namespaces**

• qpp

Quantum++ main namespace.

# 8.5.1 Detailed Description

Quantum gates.

# 8.6 classes/idisplay.h File Reference

Display interface via the non-virtual interface (NVI) and very basic JSON serialization support interface.

This graph shows which files directly or indirectly include this file:



# Classes

· class qpp::IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

· class qpp::IJSON

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

# **Namespaces**

• qpp

Quantum++ main namespace.


# 8.6.1 Detailed Description

Display interface via the non-virtual interface (NVI) and very basic JSON serialization support interface.

# 8.7 classes/init.h File Reference

Initialization.

This graph shows which files directly or indirectly include this file:



# **Classes**

· class qpp::Init

const Singleton class that performs additional initializations/cleanups

# **Namespaces**

• qpp

Quantum++ main namespace.


# 8.7.1 Detailed Description

Initialization.

# 8.8 classes/noise.h File Reference

Noise models.

This graph shows which files directly or indirectly include this file:



#### **Classes**

class qpp::NoiseType

Contains template tags used to specify the noise type.

class qpp::NoiseBase< T >

Base class for all noise models, derive your particular noise model.

• class qpp::QubitDepolarizingNoise

Qubit depolarizing noise.

• class qpp::QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

• class qpp::QubitBitFlipNoise

Qubit bit flip noise.

· class qpp::QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

• class qpp::QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

• class qpp::QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

· class qpp::QuditDepolarizingNoise

Qudit depolarizing noise.

# **Namespaces**

• qpp

Quantum++ main namespace.


# 8.8.1 Detailed Description

Noise models.

# 8.9 classes/random\_devices.h File Reference

Random devices.

This graph shows which files directly or indirectly include this file:



### Classes

• class qpp::RandomDevices

Singleton class that manages the source of randomness in the library.

# **Namespaces**

qpp

Quantum++ main namespace.


# 8.9.1 Detailed Description

Random devices.

# 8.10 classes/reversible.h File Reference

Support for classical reversible circuits.

This graph shows which files directly or indirectly include this file:



# Classes

• class qpp::Dynamic\_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime.

class qpp::Bit\_circuit

Classical reversible circuit simulator.

# **Namespaces**

• qpp

Quantum++ main namespace.


# 8.10.1 Detailed Description

Support for classical reversible circuits.

# 8.11 classes/states.h File Reference

Quantum states.

This graph shows which files directly or indirectly include this file:



#### **Classes**

· class qpp::States

const Singleton class that implements most commonly used states

# **Namespaces**

qpp

Quantum++ main namespace.

# 8.11.1 Detailed Description

Quantum states.

# 8.12 classes/timer.h File Reference

Timing.

This graph shows which files directly or indirectly include this file:



# **Classes**

class qpp::Timer < T, CLOCK\_T >
 Chronometer.

# **Namespaces**

• qpp

Quantum++ main namespace.


# 8.12.1 Detailed Description

Timing.

### 8.13 constants.h File Reference

Constants.

This graph shows which files directly or indirectly include this file:



### **Namespaces**

• qpp

Quantum++ main namespace.

· qpp::literals

### **Enumerations**

enum { qpp::RES, qpp::PROB, qpp::ST }

Constants to be used by std::get<> on the result of qpp::measure(), qpp\_measure\_seq() etc.

# **Functions**

- constexpr cplx qpp::literals::operator""\_i (unsigned long long int x) noexcept
  - User-defined literal for complex  $i = \sqrt{-1}$  (integer overload)
- constexpr cplx qpp::literals::operator""\_i (long double x) noexcept
  - User-defined literal for complex  $i = \sqrt{-1}$  (real overload)
- constexpr std::complex< float > qpp::literals::operator""\_if (unsigned long long int x) noexcept
  - User-defined literal for complex  $i = \sqrt{-1}$  (integer overload)
- constexpr std::complex< float > qpp::literals::operator""\_if (long double x) noexcept
  - User-defined literal for complex  $i = \sqrt{-1}$  (real overload)
- cplx qpp::omega (idx D)

D-th root of unity.

### Variables

• constexpr double qpp::chop = 1e-16

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

• constexpr idx qpp::maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

• constexpr double qpp::pi = 3.141592653589793238462643383279502884

 $\pi$ 

• constexpr double qpp::ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

• constexpr double <a href="mailto:qpp::infty">qpp::infty</a> = std::numeric\_limits<double>::max()

Used to denote infinity in double precision.


### 8.13.1 Detailed Description

Constants.

# 8.14 entanglement.h File Reference

Entanglement functions.

This graph shows which files directly or indirectly include this file:



### **Namespaces**

qpp

Quantum++ main namespace.

#### **Functions**

```
    template<typename Derived >

  dyn col vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector<
  idx > &dims)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  dyn_col_vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  cmat qpp::schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat <a href="mailto:qpp::schmidtA">qpp::schmidtA</a> (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Bob side.

    template<typename Derived >

  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Bob side.
• template<typename Derived >
  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx
  > &dims)
      Schmidt probabilities of the bi-partite pure state A.

    template<typename Derived >

  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt probabilities of the bi-partite pure state A.
• template<typename Derived >
  double qpp::entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Entanglement of the bi-partite pure state A.
• template<typename Derived >
  double <a href="mailto:qpp::entanglement">qpp::entanglement</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Entanglement of the bi-partite pure state A.

    template<typename Derived >

  double <a href="mailto:qpp::gconcurrence">qpp::gconcurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      G-concurrence of the bi-partite pure state A.

    template<typename Derived >

  double qpp::negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double <a href="mailto:qpp::negativity">qpp::negativity</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double <a href="mailto:qpp::concurrence">qpp::concurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.
```


### 8.14.1 Detailed Description

Entanglement functions.

# 8.15 entropies.h File Reference

Entropy functions.

This graph shows which files directly or indirectly include this file:



#### **Namespaces**

• qpp

Quantum++ main namespace.

#### **Functions**

```
    template < typename Derived >
        double qpp::entropy (const Eigen::MatrixBase < Derived > &A)
```

von-Neumann entropy of the density matrix A

double qpp::entropy (const std::vector< double > &prob)

Shannon entropy of the probability distribution prob.

 $\bullet \ \ {\sf template}{<} {\sf typename \ Derived}>$ 

```
double <a href="mailto:qpp::renyi">qpp::renyi</a> (const Eigen::MatrixBase< Derived > &A, double alpha)
```

Renyi-  $\alpha$  entropy of the density matrix A, for  $\alpha \geq 0$ .

double <a href="mailto:qpp::renyi">qpp::renyi</a> (const std::vector< double > &prob, double alpha)

Renyi-  $\alpha$  entropy of the probability distribution prob, for  $\alpha \geq 0.$ 

• template<typename Derived >

```
double qpp::tsallis (const Eigen::MatrixBase< Derived > &A, double q)
```

Tsallis- q entropy of the density matrix A, for  $q \geq 0$ .

double qpp::tsallis (const std::vector< double > &prob, double q)

Tsallis- q entropy of the probability distribution prob, for  $q \geq 0$ .

• template<typename Derived >

double qpp::qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const std::vector< idx > &subsysB, const std::vector< idx > &dims)

Quantum mutual information between 2 subsystems of a composite system.

• template<typename Derived >

 $\label{lem:double qpp::qmutualinfo} $$ double qpp::qmutualinfo (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &subsysA, const std::vector < idx > &subsysB, idx d=2) $$$ 

Quantum mutual information between 2 subsystems of a composite system.

# 8.15.1 Detailed Description

Entropy functions.

# 8.16 experimental/experimental.h File Reference

Experimental/test functions/classes.

# **Namespaces**

• qpp

Quantum++ main namespace.

• qpp::experimental

Experimental/test functions/classes, do not use or modify.


# 8.16.1 Detailed Description

Experimental/test functions/classes.

# 8.17 functions.h File Reference

Generic quantum computing functions.

This graph shows which files directly or indirectly include this file:



### Classes

• class qpp::internal::HashEigen

Functor for hashing Eigen expressions.

• class qpp::internal::EqualEigen

Functor for comparing Eigen expressions for equality.

• class qpp::internal::EqualSameSizeStringDits

Functor for comparing strings of numbers of equal sizes in lexicographical order. Establishes a strict weak ordering relation.

### **Namespaces**

qpp

Quantum++ main namespace.

- · qpp::literals
- qpp::internal

Internal utility functions, do not use them directly or modify them.

#### **Functions**

```
    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::transpose (const Eigen::MatrixBase< Derived > &A)
      Transpose.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::adjoint (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::inverse (const Eigen::MatrixBase< Derived > &A)
      Inverse.

    template<typename Derived >

  Derived::Scalar qpp::trace (const Eigen::MatrixBase< Derived > &A)
      Trace.
• template<typename Derived >
  Derived::Scalar qpp::det (const Eigen::MatrixBase< Derived > &A)
      Determinant.

    template<typename Derived >

  Derived::Scalar <a href="mailto:qpp::logdet">qpp::logdet</a> (const Eigen::MatrixBase</a> Derived > &A)
      Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar <a href="mailto:qpp::sum">qpp::sum</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise sum of A.
• template<typename Derived >
  Derived::Scalar <a href="mailto:open:prod">open:prod</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise product of A.

    template<typename Derived >

  double <a href="mailto:qpp::norm">qpp::norm</a> (const Eigen::MatrixBase< Derived > &A)
      Frobenius norm.

    template < typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::normalize (const Eigen::MatrixBase< Derived > &A)
      Normalizes state vector (column or row vector) or density matrix.

    template<typename Derived >

  std::pair< dyn_col_vect< cplx >, cmat > qpp::eig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition.
ullet template<typename Derived >
  dyn_col_vect< cplx > qpp::evals (const Eigen::MatrixBase< Derived > &A)
      Eigenvalues.

    template<typename Derived >

  cmat qpp::evects (const Eigen::MatrixBase< Derived > &A)
```

Eigenvectors.

```
• template<typename Derived >
  std::pair< dyn_col_vect< double >, cmat > qpp::heig (const Eigen::MatrixBase< Derived > &A)
     Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > qpp::hevals (const Eigen::MatrixBase< Derived > &A)
     Hermitian eigenvalues.
• template<typename Derived >
  cmat qpp::hevects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors of Hermitian matrix.

    template<typename Derived >

  std::tuple< cmat, dyn col vect< double >, cmat > qpp::svd (const Eigen::MatrixBase< Derived > &A)
     Full singular value decomposition.
• template<typename Derived >
  dyn_col_vect< double > qpp::svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.
• template<typename Derived >
  cmat qpp::svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.

    template<typename Derived >

  cmat qpp::svdV (const Eigen::MatrixBase< Derived > &A)
     Right singular vectors.

    template<typename Derived >

  cmat qpp::funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)
• template<typename Derived >
  cmat qpp::sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.
• template<typename Derived >
  cmat qpp::absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.

    template<typename Derived >

  cmat qpp::expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.
• template<typename Derived >
  cmat qpp::logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.
• template<typename Derived >
  cmat qpp::sinm (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  cmat qpp::cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.

    template<typename Derived >

  cmat qpp::spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::powm (const Eigen::MatrixBase< Derived > &A, idx n)
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

    template<typename Derived >

  double qpp::schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > qpp::cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const
  typename Derived::Scalar &))
```

```
Functor.
```

```
\bullet \ \ template {<} typename \ T >
```

dyn\_mat< typename T::Scalar > qpp::kron (const T &head)

Kronecker product.

• template<typename T , typename... Args>

dyn\_mat< typename T::Scalar > qpp::kron (const T &head, const Args &... tail)

Kronecker product.

ullet template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::kron (const std::vector< Derived > &As)

Kronecker product.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::kron (const std::initializer\_list< Derived > &As)

Kronecker product.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::kronpow (const Eigen::MatrixBase< Derived > &A, idx n)

Kronecker power.

template<typename T >

dyn\_mat< typename T::Scalar > qpp::dirsum (const T &head)

Direct sum.

• template<typename T , typename... Args>

dyn\_mat< typename T::Scalar > qpp::dirsum (const T &head, const Args &... tail)

Direct sum

ullet template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::dirsum (const std::vector< Derived > &As)

Direct sum.

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$ 

dyn\_mat< typename Derived::Scalar > qpp::dirsum (const std::initializer\_list< Derived > &As)

Direct sum.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)

Direct sum power.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::reshape (const Eigen::MatrixBase< Derived > &A, idx rows, idx cols)

Reshape.

• template<typename Derived1 , typename Derived2 >

dyn\_mat< typename Derived1::Scalar > qpp::comm (const Eigen::MatrixBase< Derived1 > &A, const Eigen::MatrixBase< Derived2 > &B)

Commutator.

 $\bullet \ \ \text{template}{<} \text{typename Derived1} \ , \\ \text{typename Derived2} >$ 

dyn\_mat< typename Derived1::Scalar > qpp::anticomm (const Eigen::MatrixBase< Derived1 > &A, const Eigen::MatrixBase< Derived2 > &B)

Anti-commutator.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::prj (const Eigen::MatrixBase< Derived > &A)

Projector

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::grams (const std::vector< Derived > &As)

Gram-Schmidt orthogonalization.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::grams (const std::initializer\_list< Derived > &As)

Gram-Schmidt orthogonalization.

template<typename Derived >

 $dyn_mat < typename Derived::Scalar > dpp::grams (const Eigen::MatrixBase < Derived > &A)$ 

Gram-Schmidt orthogonalization.

std::vector< idx > qpp::n2multiidx (idx n, const std::vector< idx > &dims)

Non-negative integer index to multi-index.

idx qpp::multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

Multi-index to non-negative integer index.

ket qpp::mket (const std::vector< idx > &mask, const std::vector< idx > &dims)

Multi-partite qudit ket.

ket qpp::mket (const std::vector< idx > &mask, idx d=2)

Multi-partite qudit ket.

cmat qpp::mprj (const std::vector < idx > &mask, const std::vector < idx > &dims)

Projector onto multi-partite qudit ket.

cmat qpp::mprj (const std::vector< idx > &mask, idx d=2)

Projector onto multi-partite qudit ket.

• template<typename InputIterator >

std::vector< double > qpp::abssq (InputIterator first, InputIterator last)

Computes the absolute values squared of an STL-like range of complex numbers.

template<typename Container >

std::vector< double > qpp::abssq (const Container &c, typename std::enable\_if< is\_iterable< Container >::value >::type \*=nullptr)

Computes the absolute values squared of an STL-like container.

template<typename Derived >

std::vector< double > qpp::abssq (const Eigen::MatrixBase< Derived > &A)

Computes the absolute values squared of an Eigen expression.

template<typename InputIterator >

std::iterator\_traits< InputIterator >::value\_type qpp::sum (InputIterator first, InputIterator last)

Element-wise sum of an STL-like range.

template<typename Container >

Container::value\_type qpp::sum (const Container &c, typename std::enable\_if< is\_iterable< Container >--:value >::type \*=nullptr)

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

std::iterator traits< InputIterator >::value type qpp::prod (InputIterator first, InputIterator last)

Element-wise product of an STL-like range.

• template<typename Container >

Container::value\_type qpp::prod (const Container &c, typename std::enable\_if < is\_iterable < Container >  $\leftarrow$  ::value >::type \*=nullptr)

Element-wise product of the elements of an STL-like container.

• template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > qpp::rho2pure (const Eigen::MatrixBase< Derived > &A)
```

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

std::vector< idx > qpp::complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

template<typename Derived >

```
std::vector< double > qpp::rho2bloch (const Eigen::MatrixBase< Derived > &A)
```

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat qpp::bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

template<char... Bits>

```
ket qpp::literals::operator""_ket ()
```

Multi-partite qubit ket user-defined literal.

template<char... Bits>

bra qpp::literals::operator""\_bra ()

Multi-partite qubit bra user-defined literal.

• template<char... Bits>

cmat qpp::literals::operator""\_prj ()

Multi-partite qubit projector user-defined literal.

template < class T >

void qpp::internal::hash\_combine (std::size\_t &seed, const T &v)

Hash combine.

template<typename Derived >

 $std::size\_t \; qpp::hash\_eigen \; (const \; Eigen::MatrixBase < \; Derived > \&A, \; std::size\_t \; seed=0)$ 

Computes the hash of en Eigen matrix/vector/expression.


# 8.17.1 Detailed Description

Generic quantum computing functions.

# 8.18 input\_output.h File Reference

Input/output functions.

This graph shows which files directly or indirectly include this file:



# **Namespaces**

qpp

Quantum++ main namespace.

### **Functions**

- template<typename Derived >
   internal::IOManipEigen qpp::disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
   Eigen expression ostream manipulator.
- internal::IOManipEigen qpp::disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

template<typename InputIterator >
 internal::IOManipRange< InputIterator > qpp::disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)

Range ostream manipulator.

template<typename Container>
 internal::IOManipRange< typename Container::const\_iterator > qpp::disp (const Container &c, const std
 ::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop, typename
 std::enable if< is iterable< Container >::value >::type \*=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

template<typename PointerType >
 internal::IOManipPointer< PointerType > qpp::disp (const PointerType \*p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)

C-style pointer ostream manipulator.

template < typename Derived > void qpp::save (const Eigen::MatrixBase < Derived > &A, const std::string &fname)

void qpp..save (const Eigen..iviathxbase< Denved > &A, const std..string &main

Saves Eigen expression to a binary file (internal format) in double precision.

 $\bullet \ \ \mathsf{template} \mathord{<} \mathsf{typename} \ \mathsf{Derived} >$ 

dyn\_mat< typename Derived::Scalar > qpp::load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.


### 8.18.1 Detailed Description

Input/output functions.

#### 8.19 instruments.h File Reference

Measurement functions.

This graph shows which files directly or indirectly include this file:



### **Namespaces**

• qpp

Quantum++ main namespace.

#### **Functions**

template<typename Derived >

dyn\_col\_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)

Generalized inner product.

template<typename Derived >

dyn\_col\_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer\_list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer\_list< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

 $\bullet \ \ \text{template}{<} \text{typename Derived} >$ 

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer\_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > qpp::measure\_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template<typename Derived >
 std::tuple< std::vector< idx >, double, cmat > qpp::measure\_seq (const Eigen::MatrixBase< Derived > &A,
 std::vector< idx > target, idx d=2)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.


### 8.19.1 Detailed Description

Measurement functions.

# 8.20 internal/classes/iomanip.h File Reference

Input/output manipulators.

This graph shows which files directly or indirectly include this file:



# Classes

- class qpp::internal::IOManipRange
   InputIterator >
- class qpp::internal::IOManipPointer< PointerType >
- class qpp::internal::IOManipEigen

# **Namespaces**

• qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


# 8.20.1 Detailed Description

Input/output manipulators.

# 8.21 internal/classes/singleton.h File Reference

Singleton pattern via CRTP.

This graph shows which files directly or indirectly include this file:



# Classes

class qpp::internal::Singleton < T >
 Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

# **Namespaces**

qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


# 8.21.1 Detailed Description

Singleton pattern via CRTP.

# 8.22 internal/util.h File Reference

Internal utility functions.

This graph shows which files directly or indirectly include this file:



#### Classes

• struct qpp::internal::Display\_Impl\_

### **Namespaces**

• qpp

Quantum++ main namespace.

qpp::internal

Internal utility functions, do not use them directly or modify them.

#### **Functions**

- void qpp::internal::n2multiidx (idx n, idx numdims, const idx \*const dims, idx \*result) noexcept
- idx qpp::internal::multiidx2n (const idx \*const midx, idx numdims, const idx \*const dims) noexcept
- template<typename Derived >
   bool qpp::internal::check\_square\_mat (const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
   bool qpp::internal::check\_vector (const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
   bool qpp::internal::check\_rvector (const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
   bool qpp::internal::check\_cvector (const Eigen::MatrixBase< Derived > &A)
- template<typename T >
   bool qpp::internal::check\_nonzero\_size (const T &x) noexcept
- template<typename T1, typename T2 >
   bool qpp::internal::check\_matching\_sizes (const T1 &lhs, const T2 &rhs) noexcept
- bool qpp::internal::check\_dims (const std::vector < idx > &dims)
- template<typename Derived >
   bool qpp::internal::check\_dims\_match\_mat (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
   bool qpp::internal::check\_dims\_match\_cvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- template<typename Derived >
   bool qpp::internal::check\_dims\_match\_rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)
- bool qpp::internal::check\_eq\_dims (const std::vector< idx > &dims, idx dim) noexcept
- bool qpp::internal::check no duplicates (std::vector< idx > v)
- bool qpp::internal::check\_subsys\_match\_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)
- template<typename Derived >
   bool qpp::internal::check\_qubit\_matrix (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
   bool qpp::internal::check\_qubit\_cvector (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
   bool qpp::internal::check\_qubit\_rvector (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
   bool qpp::internal::check\_qubit\_vector (const Eigen::MatrixBase< Derived > &A) noexcept
- bool qpp::internal::check\_perm (const std::vector< idx > &perm)
   template<typename Derived1 , typename Derived2 >
   dwn\_mat< typename Derived1 ::Sealor > generilaternal::kran2 (const Eigen::MetrivPage < Derived)</li>
- dyn\_mat< typename Derived1::Scalar > qpp::internal::kron2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::MatrixBase< Derived2 > &B)
- template<typename Derived1 , typename Derived2 >
   dyn\_mat< typename Derived1::Scalar > qpp::internal::dirsum2 (const Eigen::MatrixBase< Derived1 > &A,
   const Eigen::MatrixBase< Derived2 > &B)
- template<typename T >
   void qpp::internal::variadic\_vector\_emplace (std::vector< T > &)
- template<typename T, typename First, typename... Args>
   void qpp::internal::variadic\_vector\_emplace (std::vector< T > &v, First &&first, Args &&... args)
- idx qpp::internal::get\_num\_subsys (idx D, idx d)
- idx qpp::internal::get\_dim\_subsys (idx sz, idx N)
- template < typename T, typename std::enable\_if < std::numeric\_limits < T >::is\_iec559||is\_complex < T >::value >::type \* = nullptr > T qpp::internal::abs chop (const T &x, double chop=qpp::chop)
- template<typename T, typename std::enable\_if<!(std::numeric\_limits< T >::is\_iec559||is\_complex< T >::value)>::type \* = nullptr>
  T qpp::internal::abs\_chop (const T &x, double QPP\_UNUSED\_chop=qpp::chop)

### 8.22.1 Detailed Description

Internal utility functions.

### 8.23 MATLAB/matlab.h File Reference

Input/output interfacing with MATLAB.

```
#include "mat.h"
#include "mex.h"
```

#### **Namespaces**

qpp

Quantum++ main namespace.

#### **Functions**

template<typename Derived >
 std::enable\_if< std::is\_same< typename Derived::Scalar, cplx >::value, dyn\_mat< cplx > ::type
 qpp::loadMATLAB (const std::string &mat\_file, const std::string &var\_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable\_if<!std::is\_same< typename Derived::Scalar, cplx >::value, dyn\_mat< typename Derived::← Scalar > >::type qpp::loadMATLAB (const std::string &mat\_file, const std::string &var\_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable\_if< std::is\_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat\_file, const std::string &var\_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

• template<typename Derived >

std::enable\_if< !std::is\_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat\_file, const std::string &var\_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.


### 8.23.1 Detailed Description

Input/output interfacing with MATLAB.

# 8.24 number\_theory.h File Reference

Number theory functions.

This graph shows which files directly or indirectly include this file:



### **Namespaces**

• qpp

Quantum++ main namespace.

#### **Functions**

std::vector< int > qpp::x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double qpp::contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

• bigint qpp::gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint qpp::gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint qpp::lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint qpp::lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > qpp::invperm (const std::vector< idx > &perm)

Inverse permutation.

• std::vector< idx > qpp::compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

std::vector< bigint > qpp::factors (bigint a)

Prime factor decomposition.

• bigint <a href="mailto:dpp::modmul">dpp::modmul</a> (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

• bigint qpp::modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple < bigint, bigint, bigint > qpp::egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint qpp::modinv (bigint a, bigint p)

Modular inverse of a mod p.

• bool qpp::isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

• bigint qpp::randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

- std::vector< std::pair< int, int >> qpp::convergents (const std::vector< int > &cf)

Convergents.

• std::vector< std::pair< int, int >> qpp::convergents (double x, idx N)

Convergents.


### 8.24.1 Detailed Description

Number theory functions.

# 8.25 operations.h File Reference

Quantum operation functions.

This graph shows which files directly or indirectly include this file:



### **Namespaces**

• qpp

Quantum++ main namespace.

### **Functions**

template<typename Derived1 , typename Derived2 >
 dyn\_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 const std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1, typename Derived2 >
 dyn\_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 idx d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >
 dyn\_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const
 Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1, typename Derived2 >
 dyn\_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const
 Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived >
 cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

template<typename Derived >
 cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std
 ::vector< idx > &target, const std::vector< idx > &dims)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

• template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std ::vector< idx > &target, idx d=2)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat qpp::kraus2super (const std::vector< cmat > &Ks)

Superoperator matrix.

cmat qpp::kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector< cmat > qpp::choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

• cmat qpp::choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat qpp::super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::ptrace2 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$ 

Partial trace.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::ptrace (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial trace.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Partial transpose.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2)

Partial transpose.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &perm, const std::vector< idx > &dims)

Subsystem permutation.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &perm, idx d=2)

Subsystem permutation.

template<typename Derived >
 dyn\_mat< typename Derived::Scalar > qpp::applyQFT (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template < typename Derived >

```
dyn_mat< typename Derived::Scalar > qpp::applyTFQ (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)
```

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

dyn\_col\_vect< typename Derived::Scalar > qpp::TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > qpp::QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)
```

Qudit quantum Fourier transform.

### 8.25.1 Detailed Description

Quantum operation functions.

# 8.26 qpp.h File Reference

Quantum++ main header file, includes all other necessary headers.

```
#include <algorithm>
#include <cassert>
#include <chrono>
#include <cmath>
#include <complex>
#include <cstdlib>
#include <cstring>
#include <exception>
#include <fstream>
#include <functional>
#include <initializer_list>
#include <iomanip>
#include <iterator>
#include <limits>
#include <map>
#include <memory>
#include <numeric>
#include <ostream>
#include <random>
#include <sstream>
#include <stdexcept>
#include <string>
#include <tuple>
#include <type_traits>
#include <unordered_map>
#include <utility>
#include <vector>
```

```
#include <Eigen/Dense>
#include <Eigen/SVD>
#include "types.h"
#include "classes/exception.h"
#include "constants.h"
#include "traits.h"
#include "classes/idisplay.h"
#include "internal/util.h"
#include "internal/classes/iomanip.h"
#include "input_output.h"
#include "internal/classes/singleton.h"
#include "classes/random_devices.h"
#include "random.h"
#include "number_theory.h"
#include "functions.h"
#include "classes/init.h"
#include "classes/codes.h"
#include "classes/gates.h"
#include "classes/states.h"
#include "statistics.h"
#include "operations.h"
#include "entropies.h"
#include "entanglement.h"
#include "classes/timer.h"
#include "instruments.h"
#include "classes/reversible.h"
#include "classes/noise.h"
#include "classes/circuits/circuits.h"
#include "classes/circuits/engines.h"
```

### **Namespaces**

qpp

Quantum++ main namespace.

#### **Macros**

• #define QPP\_UNUSED\_

### 8.26.1 Detailed Description

Quantum++ main header file, includes all other necessary headers.

#### 8.26.2 Macro Definition Documentation


```
8.26.2.1 QPP_UNUSED_
```

#define QPP\_UNUSED\_

### 8.27 random.h File Reference

Randomness-related functions.

This graph shows which files directly or indirectly include this file:



### **Namespaces**

qpp

Quantum++ main namespace.

#### **Functions**

• double qpp::rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

bigint qpp::rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx qpp::randidx (idx a=std::numeric\_limits < idx >::min(), idx b=std::numeric\_limits < idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$ 

Derived qpp::rand (idx rows QPP\_UNUSED\_, idx cols QPP\_UNUSED\_, double a QPP\_UNUSED\_=0, double b QPP\_UNUSED\_=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

template<>

dmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

• template<>

cmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived qpp::randn (idx rows QPP\_UNUSED\_, idx cols QPP\_UNUSED\_, double mean QPP\_UNUSED\_=0, double sigma QPP\_UNUSED =1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

dmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

• template<>

cmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

double qpp::randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

cmat qpp::randU (idx D=2)

Generates a random unitary matrix.

cmat qpp::randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > qpp::randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat qpp::randH (idx D=2)

Generates a random Hermitian matrix.

ket qpp::randket (idx D=2)

Generates a random normalized ket (pure state vector)

• cmat qpp::randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > qpp::randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > qpp::randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.


#### 8.27.1 Detailed Description

Randomness-related functions.

# 8.28 statistics.h File Reference

Statistics functions.

This graph shows which files directly or indirectly include this file:



406 File Documentation

#### **Namespaces**

qpp

Quantum++ main namespace.

#### **Functions**

std::vector< double > qpp::uniform (idx N)

Uniform probability distribution vector.

std::vector< double > qpp::marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > qpp::marginalY (const dmat &probXY)

Marginal distribution.

• template<typename Container >

double qpp::avg (const std::vector< double > &prob, const Container &X, typename std::enable\_if< is\_ $\leftarrow$  iterable< Container >::value >::type \*=nullptr)

Average.

• template<typename Container >

double qpp::cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable\_if< is\_iterable< Container >::value >::type \*=nullptr)

Covariance.

• template<typename Container >

double qpp::var (const std::vector< double > &prob, const Container &X, typename std::enable\_if< is\_ $\leftarrow$  iterable< Container >::value >::type \*=nullptr)

Variance.

• template<typename Container >

double qpp::sigma (const std::vector< double > &prob, const Container &X, typename std::enable\_if< is\_ $\leftarrow$  iterable< Container >::value >::type \*=nullptr)

Standard deviation.

• template<typename Container >

double <a href="mailto:qpp::cor">qpp::cor</a> (const dmat &probXY, const Container &X, const Container &Y, typename std::enable\_if</a> is\_iterable</a> Container >::value >::type \*=nullptr)

Correlation.

# 8.28.1 Detailed Description


Statistics functions.

### 8.29 traits.h File Reference

Type traits.

8.29 traits.h File Reference 407

This graph shows which files directly or indirectly include this file:



#### **Classes**

```
    struct qpp::make_void < Ts >
        Helper for qpp::to_void <> alias template.
```

struct qpp::is\_iterable < T, typename >

Checks whether T is compatible with an STL-like iterable container.

• struct qpp::is\_iterable < T, to\_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(\*(std::declval < T >().end()), decltyp

struct qpp::is\_matrix\_expression< Derived >

Checks whether the type is an Eigen matrix expression.

struct qpp::is\_complex< T >

Checks whether the type is a complex type.

struct qpp::is\_complex< std::complex< T >>

Checks whether the type is a complex number type, specialization for complex types.

## **Namespaces**

• qpp

Quantum++ main namespace.

# **Typedefs**

```
    template<typename... Ts>
    using qpp::to_void = typename make_void< Ts... >::type
        Alias template that implements the proposal for void_t.
```

# 8.29.1 Detailed Description


Type traits.

408 File Documentation

# 8.30 types.h File Reference

Type aliases.

This graph shows which files directly or indirectly include this file:



# **Namespaces**

qpp

Quantum++ main namespace.

# **Typedefs**

• using qpp::idx = std::size\_t

Non-negative integer index, make sure you use an unsigned type.

• using qpp::bigint = long long int

Big integer.

• using qpp::cplx = std::complex < double >

Complex number in double precision.

• using qpp::ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector.

• using qpp::bra = Eigen::RowVectorXcd

Complex (double precision) dynamic Eigen row vector.

• using qpp::cmat = Eigen::MatrixXcd

Complex (double precision) dynamic Eigen matrix.

using qpp::dmat = Eigen::MatrixXd

Real (double precision) dynamic Eigen matrix.

 $\bullet \ \ \text{template}{<} \text{typename Scalar} >$ 

```
using qpp::dyn_mat = Eigen::Matrix< Scalar, Eigen::Dynamic, Eigen::Dynamic >
```

Dynamic Eigen matrix over the field specified by Scalar.

template<typename Scalar >

```
using qpp::dyn_col_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 >
```

Dynamic Eigen column vector over the field specified by Scalar.

template<typename Scalar >

```
using qpp::dyn_row_vect = Eigen::Matrix< Scalar, 1, Eigen::Dynamic >
```

Dynamic Eigen row vector over the field specified by Scalar.

8.30.1	Deta	halie	Desc	ription
0.50.1	שכני	alicu	DC3C	HULIUH

Type aliases.

8.31 /Users/vlad/qpp/README.md File Reference

410 File Documentation

# Index

/Users/vlad/qpp/README.md, 409	anticomm
~Bit circuit	qpp, 33
qpp::Bit_circuit, 134	any
~Codes	qpp::Dynamic bitset, 163
qpp::Codes, 141	apply
~Dynamic bitset	qpp, 33–35
qpp::Dynamic_bitset, 163	applyCTRL
~Gates	qpp, 36
qpp::Gates, 178	applyQFT
~IDisplay	qpp, 37
qpp::IDisplay, 193	applyTFQ
~IJSON	qpp, 37
qpp::IJSON, 195	avg
~Init	qpp, 38
qpp::Init, 197	ماراب من الماراب المار الماراب الماراب المارا
~NoiseBase	b00
qpp::NoiseBase< T >, 244	qpp::States, 347
~QCircuit	b01
qpp::QCircuit, 278	qpp::States, 348
~QEngine	b10
qpp::QEngine, 308	qpp::States, 348
~RandomDevices	b11
gpp::RandomDevices, 335	qpp::States, 348
~Singleton	bCNOT
qpp::internal::Singleton< T >, 339	qpp::Bit_circuit, 138
~States	begin
qpp::States, 345	qpp::QCircuit, 280
~Timer	bFRED
qpp::Timer< T, CLOCK_T >, 355	qpp::Bit_circuit, 138
qpprimor < 1, 02001(_1 > , 000	bigint
Α	qpp, 28
qpp::internal::IOManipEigen, 201	Bit_circuit
abs_chop	qpp::Bit_circuit, 133
qpp::internal, 122	bloch2rho
absm	qpp, 38
qpp, 31	bNOT
abssq	qpp::Bit_circuit, 138
qpp, 31, 32	bra
add_circuit	qpp, 28
qpp::QCircuit, 278	bSWAP
add_dit	qpp::Bit circuit, 138
qpp::QCircuit, 278	bTOF
add_hash_	app::Bit circuit, 138
qpp::QCircuit, 279	btotal
add qudit	qpp::Bit_circuit, 138
qpp::QCircuit, 279	qppbit_circuit, 130
adjoint	c_reg_
qpp, 32	qpp::QCircuit::MeasureStep, 236
all	cbegin
qpp::Dynamic_bitset, 163	qpp::QCircuit, 280
-II-  - II-  -  -  -  -  -  -  -  -  -  -  -  -  -	-li-l

•CTDI		alassas/sistes b 075
cCTRL		classes/gates.h, 375
qpp::QCircuit, 280–282		classes/idisplay.h, 376
cCTRL_custom		classes/init.h, 377
qpp::QCircuit, 282		classes/noise.h, 378
cend		classes/random_devices.h, 379
qpp::QCircuit, 283		classes/reversible.h, 379
check_cvector		classes/states.h, 380
qpp::internal, 122		classes/timer.h, 381
check_dims		cmat
qpp::internal, 123		qpp, 29
check_dims_match_cvect		cmat_hash_tbl_
qpp::internal, 123		qpp::QCircuit, 303
check_dims_match_mat		CNOT
qpp::internal, 123		qpp::Bit_circuit, 134
check_dims_match_rvect		qpp::Gates, 186
qpp::internal, 123		CNOTba
check_eq_dims		qpp::Gates, 186
qpp::internal, 123		Codes
check_matching_sizes		qpp::Codes, 141
qpp::internal, 123		codeword
check_no_duplicates		qpp::Codes, 141
qpp::internal, 124		comm
check_nonzero_size		qpp, 40
qpp::internal, 124		complement
check_perm		qpp, 40
qpp::internal, 124		compperm
check_qubit_cvector		qpp, 41
qpp::internal, 124		compute_probs_
check_qubit_matrix		qpp::NoiseBase< T >, 244
qpp::internal, 124		compute_state_
check_qubit_rvector		qpp::NoiseBase< T >, 244
qpp::internal, 124		concurrence
check qubit vector		qpp, 41
qpp::internal, 125		conjugate
check_rvector		· ·
		qpp, 41 const iterator
qpp::internal, 125		<del>_</del>
check_square_mat		qpp::QCircuit, 274
qpp::internal, 125		constants.h, 382
check_subsys_match_dims		contfrac2x
qpp::internal, 125		qpp, 42
check_vector		convergents
qpp::internal, 125		qpp, 42, 43
choi2kraus		cor
qpp, 39		qpp, 43
choi2super		cosm
qpp, 39		qpp, 44
chop		count
qpp, 118		qpp::Dynamic_bitset, 163
chop_		count_
qpp::internal::IOManipEigen, 201		qpp::Bit_circuit, 138
qpp::internal::IOManipPointer< PointerType	>,	qpp::QCircuit, 303
204		cov
qpp::internal::IOManipRange< InputIterator	· >,	qpp, 44
207		cplx
classes/circuits/circuits.h, 371		qpp, 29
classes/circuits/engines.h, 372		CTRL
classes/codes.h, 373		qpp::Gates, 179
classes/exception.h, 373		qpp::QCircuit, 283, 284
•		

ctrl_	qpp::exception::Unknown, 363
qpp::QCircuit::GateStep, 190	qpp::exception::ZeroSize, 369
CTRL_custom	det
qpp::QCircuit, 285	qpp, 45
CUSTOM	difference_type
qpp::QCircuit, 275	qpp::QCircuit::iterator, 215
CUSTOM_cCTRL	dirsum
qpp::QCircuit, 275	qpp, 45–47
CUSTOM_CTRL	dirsum2
qpp::QCircuit, 275	qpp::internal, 125
CustomException	dirsumpow
qpp::exception::CustomException, 143	qpp, 47
cwise	disp
qpp, 45	qpp, 48–50
CZ	display
qpp::Gates, 186	qpp::Dynamic_bitset, 164
٨	qpp::IDisplay, 193
d_ consultaine Page < T > 049	qpp::internal::IOManipEigen, 201
qpp::NoiseBase< T >, 248	<pre>qpp::internal::IOManipPointer&lt; PointerType &gt;,</pre>
qpp::QCircuit, 303	203
data	qpp::internal::IOManipRange< InputIterator >,
qpp::Dynamic_bitset, 163	207
depth_	qpp::QCircuit, 285
qpp::Bit_circuit, 139	qpp::QCircuit::iterator::value_type_, 366
description	qpp::QEngine, 308
qpp::exception::CustomException, 144	qpp::Timer< T, CLOCK_T >, 356
qpp::exception::DimsInvalid, 146	display_impl_
qpp::exception::DimsMismatchCvector, 148	qpp::internal::Display_Impl_, 157
qpp::exception::DimsMismatchMatrix, 150 qpp::exception::DimsMismatchRvector, 152	dits_
qpp::exception::DimsMismatchVector, 152 qpp::exception::DimsMismatchVector, 154	qpp::QEngine, 314
	dmat
<pre>qpp::exception::DimsNotEqual, 156 qpp::exception::Duplicates, 159</pre>	qpp, 29
qpp::exception::Exception, 175	dyn_col_vect
	qpp, 29
qpp::exception::InvalidIterator, 199	dyn_mat
<pre>qpp::exception::MatrixMismatchSubsys, 221 qpp::exception::MatrixNotCvector, 224</pre>	qpp, 29
qpp::exception::MatrixNotOvector, 224 qpp::exception::MatrixNotRvector, 226	dyn_row_vect
qpp::exception::MatrixNotNector, 228	qpp, 30
qpp::exception::MatrixNotSquareNorCvector, 230	Dynamic_bitset
qpp::exception::MatrixNotSquareNorRvector, 232	qpp::Dynamic_bitset, 162
qpp::exception::MatrixNotSquareNorVector, 234	ee
qpp::exception::MatrixNot/Squarervorvector, 234	qpp, 118
app::exception::NoCodeword, 240	egcd
qpp::exception::NotBipartite, 251	qpp, 50
app::exception::NotImplemented, 253	eig
qpp::exception::NotQubitCvector, 255	qpp, 51
qpp::exception::NotQubitMatrix, 257	elem_
qpp::exception::NotQubitRvector, 259	qpp::QCircuit::iterator, 219
qpp::exception::NotQubitSubsys, 261	end
qpp::exception::NotQubitVector, 263	qpp::QCircuit, 286
qpp::exception::OutOfRange, 265	end_
qpp::exception::PermInvalid, 267	<pre>qpp::internal::IOManipPointer&lt; PointerType &gt;,</pre>
qpp::exception::PermMismatchDims, 269	204
qpp::exception::QuditAlreadyMeasured, 330	qpp::internal::IOManipRange< InputIterator >,
qpp::exception::SizeMismatch, 341	208
qpp::exception::SubsysMismatchDims, 353	qpp::Timer< T, CLOCK_T >, 357
qpp::exception::TypeMismatch, 359	entanglement
qpp::exception::UndefinedType, 361	qpp, 51, 52
-1126	- PP

entanglement.h, 383	fill_Ks_	
entropies.h, 385	qpp::QuditDepolarizingNoise, 333	
entropy	fill probs	
qpp, 52	qpp::QuditDepolarizingNoise, 333	
evals	first_	
qpp, 53	qpp::internal::IOManipRange< InputIterator >,	
evects	208	
qpp, 53	FIVE QUBIT	
	qpp::Codes, 140	
Exception qpp::exception::DimsInvalid, 146	flip	
	•	
qpp::exception::DimsMismatchCvector, 148 qpp::exception::DimsMismatchMatrix, 150	qpp::Dynamic_bitset, 164 FRED	
qpp::exception::DimsMismatchRvector, 152		
	qpp::Bit_circuit, 134	
qpp::exception::DimsMismatchVector, 154	qpp::Gates, 186	
qpp::exception::DimsNotEqual, 156	functions.h, 386	
qpp::exception::Duplicates, 159	funm	
app::exception::Exception, 175	qpp, 54	
qpp::exception::InvalidIterator, 199	GATE	
qpp::exception::MatrixMismatchSubsys, 222	qpp::QCircuit, 277	
qpp::exception::MatrixNotCvector, 224	gate	
qpp::exception::MatrixNotRvector, 226	qpp::QCircuit, 286, 287	
qpp::exception::MatrixNotSquare, 228	gate custom	
qpp::exception::MatrixNotSquareNorCvector, 230	qpp::QCircuit, 288	
qpp::exception::MatrixNotSquareNorRvector, 232	gate_fan	
qpp::exception::MatrixNotSquareNorVector, 234	qpp::QCircuit, 288, 289	
qpp::exception::MatrixNotVector, 236	gate_hash_	
qpp::exception::NoCodeword, 240	qpp::QCircuit::GateStep, 190	
qpp::exception::NotBipartite, 251		
qpp::exception::NotImplemented, 253	gate_type_ qpp::QCircuit::GateStep, 191	
qpp::exception::NotQubitCvector, 255	Gates	
qpp::exception::NotQubitMatrix, 257		
qpp::exception::NotQubitRvector, 259	qpp::Gates, 178	
qpp::exception::NotQubitSubsys, 261	gates_	
qpp::exception::NotQubitVector, 263	qpp::QCircuit, 303	
qpp::exception::OutOfRange, 265	gates_ip_	
qpp::exception::PermInvalid, 267	qpp::QCircuit::iterator::value_type_, 366	
qpp::exception::PermMismatchDims, 269	GateStep	
qpp::exception::QuditAlreadyMeasured, 331	qpp::QCircuit::GateStep, 190	
qpp::exception::SizeMismatch, 341	GateType	
qpp::exception::SubsysMismatchDims, 353	qpp::QCircuit, 275	
qpp::exception::TypeMismatch, 359	gcd	
qpp::exception::UndefinedType, 361	qpp, 55	
qpp::exception::Unknown, 363	gconcurrence	
qpp::exception::ZeroSize, 369	qpp, 56	
execute	generated_	
qpp::QEngine, 309	qpp::NoiseBase< T >, 248	
qpp::QNoisyEngine < NoiseModel >, 318, 319	get	
expandout	qpp::Dynamic_bitset, 165	
qpp::Gates, 179–181	get_circuit	
experimental/experimental.h, 386	qpp::QEngine, 310	
expm	get_cmat_hash_tbl_	
qpp, 54	qpp::QCircuit, 289	
	get_d	
factors	qpp::NoiseBase< T >, 245	
qpp, 54	qpp::QCircuit, 289	
FAN	get_depth	
qpp::QCircuit, 275	qpp::QCircuit, 290	
Fd	get_dim_subsys	
qpp::Gates, 181	qpp::internal, 126	

. 19	0.01 11 000
get_dit	qpp::QCircuit, 293
qpp::QEngine, 310	get_thread_local_instance
get_dits	qpp::internal::Singleton $<$ T $>$ , 339
qpp::QEngine, 310	GHZ
get_duration	qpp::States, 348
qpp::Timer< T, CLOCK_T >, 356	grams
get_gate_count	qpp, 56, 57
	<b>чрр</b> , σσ, σ <i>γ</i>
qpp::Bit_circuit, 135	Н
qpp::QCircuit, 290	
get_gate_depth	qpp::Gates, 187
qpp::Bit_circuit, 135	hash_combine
get_gates_	qpp::internal, 126
qpp::QCircuit, 291	hash_eigen
get instance	qpp, 57
· -	heig
qpp::internal::Singleton < T >, 339	qpp, 58
get_Ks	hevals
qpp::NoiseBase< T >, 245	qpp, 58
get_last_idx	
qpp::NoiseBase< T >, 245	hevects
get_last_K	qpp, 59
gpp::NoiseBase< T >, 246	
get_last_p	i_
	qpp::NoiseBase< T >, 248
qpp::NoiseBase< T >, 246	ld
get_measured	qpp::Gates, 182
qpp::QCircuit, 291	ld2
qpp::QEngine, 310, 311	qpp::Gates, 187
get_measurement_count	idx
qpp::QCircuit, 291, 292	
get measurements	qpp, 30
gpp::QCircuit, 292	index_
	qpp::Dynamic_bitset, 165
get_name	infty
qpp::Gates, 182	qpp, 118
qpp::QCircuit, 292	Init
get_nc	qpp::Init, 197
qpp::QCircuit, 292	input_output.h, 391
get_noise_results	instruments.h, 392
qpp::QNoisyEngine < NoiseModel >, 319	internal/classes/iomanip.h, 394
get non measured	•
qpp::QCircuit, 293	internal/classes/singleton.h, 395
	internal/util.h, 395
qpp::QEngine, 311	internal::Singleton< const Codes >
get_nop_count	qpp::Codes, 141
qpp::QCircuit, 293	internal::Singleton< const Gates >
get_nq	qpp::Gates, 186
qpp::QCircuit, 293	internal::Singleton< const Init >
get_num_subsys	qpp::Init, 197
gpp::internal, 126	internal::Singleton< const States >
get prng	
<u> </u>	qpp::States, 347
qpp::RandomDevices, 336	internal::Singleton< RandomDevices >
get_probs	qpp::RandomDevices, 337
qpp::NoiseBase $<$ T $>$ , 246	inverse
qpp::QEngine, 311	qpp, 59
get_psi	invperm
qpp::QEngine, 311	qpp, 60
get_relative_pos_	IOManipEigen
qpp::QEngine, 312	qpp::internal::IOManipEigen, 201
get_stats	IOManipPointer
qpp::QEngine, 312	qpp::internal::IOManipPointer< PointerType >
get_step_count	203

IOManipRange	measure
qpp::internal::IOManipRange< InputIterator >,	qpp, 71–75
206, 207	measure_seq
ip	qpp, 76, 77
qpp, 60, 61	MEASURE_V
ip_ and uCCive vitalite vertex value to the control of the control	qpp::QCircuit, 277
qpp::QCircuit::iterator::value_type_, 367 isprime	MEASURE_V_MANY
qpp, 61	qpp::QCircuit, 277 MEASURE Z
iterator	qpp::QCircuit, 277
qpp::QCircuit::iterator, 216	MEASURE Z MANY
iterator_category	qpp::QCircuit, 277
qpp::QCircuit::iterator, 215	measured_
	qpp::QCircuit, 303
jn OLL OLE	MEASUREMENT
qpp::States, 345	qpp::QCircuit, 277
kat	measurement_count_
ket	qpp::QCircuit, 303
qpp, 30 kraus2choi	measurement_type_
qpp, 61	qpp::QCircuit::MeasureStep, 238
kraus2super	measurements_
qpp, 62	qpp::QCircuit, 304
kron	measurements_ip_
qpp, 62, 64, 65	qpp::QCircuit::iterator::value_type_, 367
qpp::QCircuit, 294	MeasureStep
kron2	qpp::QCircuit::MeasureStep, 237, 238
qpp::internal, 126	MeasureType
kronpow	qpp::QCircuit, 275
qpp, 65	measureV
Ks_	qpp::QCircuit, 295
qpp::NoiseBase< T >, 248	measureZ qpp::QCircuit, 296
	mes
last_	qpp::States, 345
qpp::internal::IOManipRange< InputIterator >,	minus
208	qpp::States, 346
lcm	mket
qpp, 66	qpp, 77, 78
load	modinv
qpp, 67	qpp, 78
qpp::RandomDevices, 336 loadMATLAB	MODMUL
qpp, 67, 68	qpp::Gates, 183
logdet	modmul
qpp, 68	qpp, 79
logm	modpow
qpp, 69	qpp, 79
lognegativity	mprj
qpp, 69, 70	qpp, 80
	msg_
marginalX	qpp::exception::Exception, 176
qpp, 70	multiidx2n
marginalY	qpp, 81
qpp, 70	qpp::internal, 127
MATLAB/matlab.h, 397	MULTIPLE_cCTRL_MULTIPLE_TARGET
mats_hash_	qpp::QCircuit, 275
qpp::QCircuit::MeasureStep, 238	MULTIPLE_cCTRL_SINGLE_TARGET
maxn	qpp::QCircuit, 275
qpp, 118	MULTIPLE_CTRL_MULTIPLE_TARGET

	qpp::QCircuit, 275 TIPLE_CTRL_SINGLE_TARGET qpp::QCircuit, 275		<pre>qpp::QCircuit::iterator, 217 operator&lt;&lt;     qpp::IDisplay, 194     qpp::QCircuit 301, 303</pre>	
n2mı	ultiidx		qpp::QCircuit, 301, 302 operator()	
	qpp, 81		qpp::internal::EqualEigen, 171	
	qpp::internal, 127		qpp::internal::EqualSameSizeStringDits, 172	
N_	,		qpp::internal::HashEigen, 192	
_	qpp::internal::IOManipPointer< PointerType	>,	qpp::NoiseBase< T >, 246, 247	
	204	ŕ	operator++	
n_			qpp::QCircuit::iterator, 217	
	qpp::Dynamic_bitset, 170		operator-	
name			qpp::Dynamic_bitset, 166	
	qpp::QCircuit, 304		operator=	
	qpp::QCircuit::GateStep, 191		qpp::internal::IOManipPointer< PointerType	>,
	qpp::QCircuit::MeasureStep, 238		204	,
nc_			qpp::internal::IOManipRange< InputIterator	>,
	qpp::QCircuit, 304		207	ŕ
nega	itivity		qpp::internal::Singleton< T >, 339	
	qpp, 82		qpp::QCircuit::iterator, 217	
NINE	_QUBIT_SHOR		qpp::QCircuit::iterator::value_type_, 366	
	qpp::Codes, 140		qpp::QEngine, 312	
noise	9_		operator==	
	qpp::QNoisyEngine < NoiseModel >, 319		qpp::Dynamic_bitset, 167	
noise	e_results_		qpp::QCircuit::iterator, 218	
	qpp::QNoisyEngine < NoiseModel >, 319		operator""_bra	
noise	e_type		qpp::literals, 128	
	qpp::NoiseBase< T >, 243		operator""_i	
	eBase		qpp::literals, 128, 129	
	qpp::NoiseBase< T >, 243		operator""_if	
NON			qpp::literals, 129	
	qpp::QCircuit, 275, 277		operator""_ket	
none			qpp::literals, 129	
	qpp::Dynamic_bitset, 165		operator""_prj	
NOP			qpp::literals, 130	
	qpp::QCircuit, 277			
nop			P Paintage   Pa	
	qpp::QCircuit, 296		qpp::internal::IOManipPointer< PointerType	>,
norm			204	
	qpp, 83		pb00	
norm	nalize		qpp::States, 348	
NOT	qpp, 83		pb01	
NOT			qpp::States, 348 pb10	
	qpp::Bit_circuit, 136		qpp::States, 349	
nq_	annu OCircuit 204		pb11	
امريم	qpp::QCircuit, 304		qpp::States, 349	
numi	per_theory.h, 398		pGHZ	
offse	t		qpp::States, 349	
	qpp::Dynamic_bitset, 166		pi	
ome			qpp, 118	
00	qpp, 83		plus	
one	TIET / Z		qpp::States, 346	
	qpp::States, 346		pointer	
	ations.h, 400		qpp::QCircuit::iterator, 215	
•	ator *		powm	
	qpp::QCircuit::iterator, 216		qpp, 84	
	ator!=		prj	
	qpp::Dynamic_bitset, 166		qpp, 84	

prng_	bigint, 28
qpp::RandomDevices, 337	bloch2rho, 38
PROB	bra, 28
qpp, 31	choi2kraus, 39
probs_	choi2super, 39
qpp::NoiseBase< T >, 248	chop, 118
qpp::QEngine, 315	cmat, 29
prod	comm, 40
qpp, 85	complement, 40
psi_	compperm, 41
qpp::QEngine, 315	concurrence, 41
ptrace	conjugate, 41
qpp, 86	contfrac2x, 42
ptrace1	convergents, 42, 43
gpp, 87	cor, 43
ptrace2	
qpp, 88	cosm, 44
ptranspose	cov, 44
• •	cplx, 29
qpp, 89	cwise, 45
pW	det, 45
qpp::States, 349	dirsum, 45–47
px0	dirsumpow, 47
qpp::States, 349	disp, 48–50
px1	dmat, 29
qpp::States, 349	dyn_col_vect, 29
py0	dyn_mat, 29
qpp::States, 350	dyn_row_vect, 30
py1	ee, 118
qpp::States, 350	egcd, 50
pz0	eig, 51
qpp::States, 350	entanglement, 51, 52
pz1	
qpp::States, 350	entropy, 52
	evals, 53
qc_	evects, 53
qpp::QCircuit::iterator, 219	expm, 54
qpp::QEngine, 315	factors, 54
QCircuit	funm, 54
qpp::QCircuit, 277	gcd, 55
QEngine	gconcurrence, 56
qpp::QCircuit, 302	grams, <mark>56</mark> , 57
qpp::QEngine, 307, 308	hash_eigen, 57
QFT	heig, 58
qpp, 90	hevals, 58
qpp::QCircuit, 297, 298	hevects, 59
gmutualinfo	idx, 30
qpp, 90, 91	infty, 118
QNoisyEngine	inverse, 59
qpp::QNoisyEngine < NoiseModel >, 317	invperm, 60
qpp, 15	ip, 60, 61
absm, 31	isprime, 61
abssq, 31, 32	ket, 30
•	kraus2choi, 61
adjoint, 32	kraus2super, 62
anticomm, 33	
apply, 33–35	kron, 62, 64, 65
applyCTRL, 36	kronpow, 65
applyQFT, 37	lcm, 66
applyTFQ, 37	load, 67
avg, 38	loadMATLAB, 67, 68

logdet, 68	ST, 31
logm, 69	sum, 110, 111
lognegativity, 69, 70	super2choi, 111
marginalX, 70	svals, 112
marginalY, 70	svd, 112
maxn, 118	svdU, 112
measure, 71–75	svdV, 113
measure_seq, 76, 77	syspermute, 113, 114
mket, 77, 78	TFQ, 114
modinv, 78	to_void, 30
modmul, 79	trace, 114
modpow, 79	transpose, 115
mprj, 80	tsallis, 115, 116
multiidx2n, 81	uniform, 116
n2multiidx, 81	var, 117
negativity, 82	x2contfrac, 117
norm, 83	qpp.h, 402
normalize, 83	QPP_UNUSED_, 403
omega, 83	qpp::Bit_circuit, 131
pi, 118	~Bit_circuit, 134
powm, 84	bCNOT_, 138
prj, 84	bFRED_, 138
PROB, 31	Bit circuit, 133
	<del>-</del> '
prod, 85	bNOT_, 138
ptrace, 86	bSWAP_, 138
ptrace1, 87	bTOF_, 138
ptrace2, 88	btotal_, 138
ptranspose, 89	CNOT, 134
QFT, 90	count_, 138
qmutualinfo, 90, 91	depth_, 139
rand, 91–93	FRED, 134
randH, 94	get_gate_count, 135
randidx, 94	get_gate_depth, 135
randket, 94	NOT, 136
randkraus, 95	reset, 136
randn, 95–97	SWAP, 136
randperm, 97	TOF, 137
randprime, 97	X, 137
randprob, 99	qpp::Codes, 139
randrho, 99	$\sim$ Codes, 141
randU, 99	Codes, 141
randV, 100	codeword, 141
renyi, 100, 101	FIVE_QUBIT, 140
RES, 31	internal::Singleton < const Codes >, 141
reshape, 101	NINE_QUBIT_SHOR, 140
rho2bloch, 102	SEVEN_QUBIT_STEANE, 140
rho2pure, 102	Type, 140
save, 103	qpp::Dynamic_bitset, 159
saveMATLAB, 103, 104	$\sim$ Dynamic_bitset, 163
schatten, 104	all, 163
schmidtA, 105	any, 163
schmidtB, 105, 106	count, 163
schmidtcoeffs, 106, 107	data, 163
schmidtprobs, 107, 108	display, 164
sigma, 108	Dynamic_bitset, 162
sinm, 109	flip, 164
spectralpowm, 109	get, 165
sqrtm, 110	index_, 165

n_, 170	description, 226
none, 165	Exception, 226
offset_, 166	qpp::exception::MatrixNotSquare, 226
operator!=, 166	description, 228
operator-, 166	Exception, 228
operator==, 167	qpp::exception::MatrixNotSquareNorCvector, 228
rand, 167, 168	description, 230
reset, 168	Exception, 230
set, 168, 169	qpp::exception::MatrixNotSquareNorRvector, 230
size, 169	description, 232
storage_size, 169	Exception, 232
storage_size_, 170	qpp::exception::MatrixNotSquareNorVector, 232
storage_type, 162	description, 234
to_string, 169	Exception, 234
v_, 170	qpp::exception::MatrixNotVector, 234
value_type, 162	description, 236
qpp::exception, 118	Exception, 236
qpp::exception::CustomException, 142	qpp::exception::NoCodeword, 239
CustomException, 143	description, 240
description, 144	Exception, 240
what_, 144	qpp::exception::NotBipartite, 249
qpp::exception::DimsInvalid, 145	description, 251
description, 146	Exception, 251
Exception, 146	qpp::exception::NotImplemented, 251
qpp::exception::DimsMismatchCvector, 147	description, 253
description, 148	Exception, 253
Exception, 148	qpp::exception::NotQubitCvector, 253
qpp::exception::DimsMismatchMatrix, 149	description, 255
description, 150	Exception, 255
Exception, 150	qpp::exception::NotQubitMatrix, 255
qpp::exception::DimsMismatchRvector, 151	description, 257
description, 152	Exception, 257
Exception, 152	qpp::exception::NotQubitRvector, 257
qpp::exception::DimsMismatchVector, 153	description, 259
description, 154	Exception, 259
Exception, 154	qpp::exception::NotQubitSubsys, 259
qpp::exception::DimsNotEqual, 155	description, 261
description, 156	Exception, 261
Exception, 156	qpp::exception::NotQubitVector, 261
qpp::exception::Duplicates, 158	description, 263
description, 159	Exception, 263
Exception, 159	qpp::exception::OutOfRange, 263
qpp::exception::Exception, 173	description, 265
description, 175	Exception, 265
Exception, 175	qpp::exception::PermInvalid, 265
msg_, 176	description, 267
what, 175	Exception, 267
where_, 176	qpp::exception::PermMismatchDims, 267
qpp::exception::InvalidIterator, 197	description, 269
description, 199	Exception, 269
Exception, 199	qpp::exception::QuditAlreadyMeasured, 329
qpp::exception::MatrixMismatchSubsys, 220	description, 330
description, 221	Exception, 331
Exception, 222	qpp::exception::SizeMismatch, 340
qpp::exception::MatrixNotCvector, 222	description, 341
description, 224	Exception, 341
Exception, 224	qpp::exception::SubsysMismatchDims, 352
qpp::exception::MatrixNotRvector, 224	description, 353

Exception, 353	check dims, 123
qpp::exception::TypeMismatch, 358	check_dims_match_cvect, 123
description, 359	check dims match mat, 123
Exception, 359	check_dims_match_rvect, 123
qpp::exception::UndefinedType, 360	check_eq_dims, 123
description, 361	check matching sizes, 123
Exception, 361	check_no_duplicates, 124
qpp::exception::Unknown, 362	check_nonzero_size, 124
description, 363	check_perm, 124
Exception, 363	check qubit cvector, 124
qpp::exception::ZeroSize, 368	check qubit matrix, 124
description, 369	check_qubit_rvector, 124
Exception, 369	check_qubit_vector, 125
qpp::experimental, 120	check_rvector, 125
qpp::Gates, 176	check_square_mat, 125
∼Gates, 178	check_subsys_match_dims, 125
CNOT, 186	check_vector, 125
CNOTba, 186	dirsum2, 125
CTRL, 179	get_dim_subsys, 126
CZ, 186	get_num_subsys, 126
expandout, 179–181	hash_combine, 126
Fd, 181	kron2, 126
FRED, 186	multiidx2n, 127
Gates, 178	n2multiidx, 127
get_name, 182	variadic_vector_emplace, 127
H, 187	qpp::internal::Display_Impl_, 157
ld, 182	display_impl_, 157
ld2, 187	qpp::internal::EqualEigen, 171
internal::Singleton< const Gates >, 186	operator(), 171
MODMUL, 183	qpp::internal::EqualSameSizeStringDits, 172
Rn, 183	operator(), 172
RX, 184	qpp::internal::HashEigen, 191
RY, 184	operator(), 192
RZ, 184	qpp::internal::IOManipEigen, 199
S, 187	A_, 201
SWAP, 187	 chop_, 201
SWAPd, 185	display, 201
T, 187	IOManipEigen, 201
TOF, 187	qpp::internal::IOManipPointer< PointerType >, 202
X, 188	chop_, 204
Xd, 185	display, 203
Y, 188	end_, 204
Z, 188	IOManipPointer, 203
Zd, 185	N_, 204
qpp::IDisplay, 192	operator=, 204
∼IDisplay, 193	p_, 204
display, 193	separator_, 205
operator<<, 194	start_, 205
qpp::IJSON, 194	qpp::internal::IOManipRange< InputIterator >, 205
∼IJSON, 195	chop_, 207
to_JSON, 195	display, 207
qpp::Init, 195	end_, 208
~Init, 197	first_, 208
Init, 197	IOManipRange, 206, 207
internal::Singleton< const Init >, 197	last_, 208
qpp::internal, 120	operator=, 207
abs_chop, 122	separator_, 208
check_cvector, 122	start_, 208

	CTDL sustant 005
qpp::internal::Singleton < T >, 337	CTRL_custom, 285
~Singleton, 339	CUSTOM, 275
get_instance, 339	CUSTOM_cCTRL, 275
get_thread_local_instance, 339	CUSTOM_CTRL, 275
operator=, 339	d_, 303
Singleton, 338	display, 285
app::is_complex < std::complex < T > >, 210	end, 286
qpp::is_complex < T >, 209	FAN, 275
qpp::is_iterable < T, to_void < decltype(std::declval <	GATE, 277
T >().begin()), decltype(std::declval< T	gate, 286, 287
>().end()), decltype(*(std::declval< T	gate_custom, 288
>().begin()))> >, 212	gate_fan, 288, 289
qpp::is_iterable < T, typename >, 211	gates_, 303
qpp::is_matrix_expression< Derived >, 213	GateType, 275
qpp::literals, 128	get_cmat_hash_tbl_, 289
operator""_bra, 128	get_d, 289
operator""_i, 128, 129	get_depth, 290
operator""_if, 129	get_gate_count, 290
operator""_ket, 129	get_gates_, 291
operator""_prj, 130	get_measured, 291
qpp::make_void< Ts >, 219	get_measurement_count, 291, 292
type, 220	get_measurements_, 292
qpp::NoiseBase< T >, 241	get_name, 292
∼NoiseBase, 244	get_nc, 292
compute_probs_, 244	get_non_measured, 293
compute_state_, 244	get_nop_count, 293
d_, 248	get_nq, 293
generated_, 248	get_step_count, 293
get_d, 245	kron, 294
get_Ks, 245	MEASURE_V, 277
get_last_idx, 245	MEASURE_V_MANY, 277
get_last_K, 246	MEASURE_Z, 277
get_last_p, 246	MEASURE_Z_MANY, 277
get_probs, 246	measured_, 303
i_, 248	MEASUREMENT, 277
Ks_, 248	measurement_count_, 303
noise_type, 243	measurements_, 304
NoiseBase, 243	MeasureType, 275
operator(), 246, 247	measureV, 295
probs_, 248	measureZ, 296
qpp::NoiseType, 249	MULTIPLE_cCTRL_MULTIPLE_TARGET, 275
qpp::NoiseType::StateDependent, 342	MULTIPLE_cCTRL_SINGLE_TARGET, 275
qpp::NoiseType::StateIndependent, 342	MULTIPLE_CTRL_MULTIPLE_TARGET, 275
qpp::QCircuit, 270	MULTIPLE_CTRL_SINGLE_TARGET, 275
∼QCircuit, 278	name_, 304
add_circuit, 278	nc_, 304
add_dit, 278	NONE, 275, 277
add_hash_, 279	NOP, 277
add_qudit, 279	nop, 296
begin, 280	nq_, 304
cbegin, 280	operator<<, 301, 302
cCTRL, 280-282	QCircuit, 277
cCTRL_custom, 282	QEngine, 302
cend, 283	QFT, 297, 298
cmat_hash_tbl_, 303	replicate, 298
const_iterator, 274	SINGLE, 275
count_, 303	SINGLE_cCTRL_MULTIPLE_TARGET, 275
CTRL, 283, 284	SINGLE_cCTRL_SINGLE_TARGET, 275
	·

SINGLE_CTRL_MULTIPLE_TARGET, 275	get_psi, 311
SINGLE_CTRL_SINGLE_TARGET, 275	get_relative_pos_, 312
step_types_, 304	get_stats, 312
StepType, 277	operator=, 312
TFQ, 298, 300	probs_, 315
THREE, 275	psi_, 315
to_JSON, 300	qc_, 315
TWO, 275	QEngine, 307, 308
qpp::QCircuit::GateStep, 189	reset, 312
ctrl_, 190	reset_stats, 313
gate_hash_, 190	set_dit, 313
gate_type_, 191	set_measured_, 313
GateStep, 190	set_psi, 314
name_, 191	stats_, 315
target_, 191	subsys_, 315
qpp::QCircuit::iterator, 214	to_JSON, 314
difference_type, 215	qpp::QNoisyEngine < NoiseModel >, 316
elem_, 219	execute, 318, 319
iterator, 216	get_noise_results, 319
iterator_category, 215	noise_, 319
operator *, 216	noise_results_, 319
operator!=, 217	QNoisyEngine, 317
operator++, 217	qpp::QubitAmplitudeDampingNoise, 320
operator=, 217	QubitAmplitudeDampingNoise, 321
operator==, 218	qpp::QubitBitFlipNoise, 321
pointer, 215	QubitBitFlipNoise, 323
qc_, 219	qpp::QubitBitPhaseFlipNoise, 323
reference, 216	QubitBitPhaseFlipNoise, 324
set_begin_, 218	qpp::QubitDepolarizingNoise, 325
set_end_, 218	QubitDepolarizingNoise, 326
value_type, 216	qpp::QubitPhaseDampingNoise, 326
qpp::QCircuit::iterator::value_type_, 364	QubitPhaseDampingNoise, 327
display, 366	qpp::QubitPhaseFlipNoise, 328
gates_ip_, 366	QubitPhaseFlipNoise, 329
ip_, 367	qpp::QuditDepolarizingNoise, 331
measurements_ip_, 367	fill_Ks_, 333
operator=, 366	fill_probs_, 333
type_, 367	QuditDepolarizingNoise, 332
value_type_, 365, 366	qpp::RandomDevices, 334
value_type_qc_, 367	$\sim$ RandomDevices, 335
qpp::QCircuit::MeasureStep, 236	get_prng, 336
c_reg_, 238	internal::Singleton< RandomDevices >, 337
mats_hash_, 238	load, 336
measurement_type_, 238	prng_, 337
MeasureStep, 237, 238	RandomDevices, 335
name_, 238	rd_, 337
target_, 239	save, 336
qpp::QEngine, 305	qpp::States, 342
∼QEngine, 308	$\sim$ States, 345
display, 308	b00, 347
dits_, 314	b01, 348
execute, 309	b10, 348
get_circuit, 310	b11, 348
get_dit, 310	GHZ, 348
get_dits, 310	internal::Singleton< const States >, 347
get_measured, 310, 311	jn, 345
get_non_measured, 311 get_probs, 311	mes, 345
ger_props, or r	minus, 346

one, 346	randkraus		
pb00, 348	qpp, 95		
pb01, 348	randn		
pb10, 349	qpp, 95–97		
pb11, 349	random.h, 404		
pGHZ, 349	RandomDevices		
plus, 346	qpp::RandomDevices, 335		
pW, 349	randperm		
px0, 349	qpp, 97		
px1, 349	randprime		
py0, 350	qpp, 97		
py1, 350	randprob		
pz0, 350	qpp, 99		
pz1, 350	randrho		
States, 345	qpp, 99		
W, 350	randU		
x0, 350	qpp, 99		
x1, 351	randV		
y0, <mark>351</mark>	qpp, 100		
y1, <mark>35</mark> 1	rd_		
z0, <u>351</u>	qpp::RandomDevices, 337		
z1, <u>35</u> 1	reference		
zero, 347	qpp::QCircuit::iterator, 216		
qpp::Timer $<$ T, CLOCK_T $>$ , 354	renyi		
$\sim$ Timer, 355	qpp, 100, 101		
display, 356	replicate		
end_, 357	qpp::QCircuit, 298		
get_duration, 356	RES		
start_, 357	qpp, 31		
tic, 356	reset		
tics, 357	qpp::Bit_circuit, 136		
Timer, 355	qpp::Dynamic_bitset, 168		
toc, 357	qpp::QEngine, 312		
QPP_UNUSED_	reset_stats		
qpp.h, 403	qpp::QEngine, 313		
QubitAmplitudeDampingNoise	reshape		
qpp::QubitAmplitudeDampingNoise, 321	qpp, 101 rho2bloch		
QubitBitFlipNoise			
qpp::QubitBitFlipNoise, 323	qpp, 102		
QubitBitPhaseFlipNoise qpp::QubitBitPhaseFlipNoise, 324	rho2pure		
	qpp, 102 Rn		
QubitDepolarizingNoise			
<pre>qpp::QubitDepolarizingNoise, 326 QubitPhaseDampingNoise</pre>	qpp::Gates, 183		
qpp::QubitPhaseDampingNoise, 327			
QubitPhaseFlipNoise	qpp::Gates, 184 RY		
qpp::QubitPhaseFlipNoise, 329			
	qpp::Gates, 184		
QuditDepolarizingNoise	qpp::Gates, 184 RZ		
qpp::QuditDepolarizingNoise, 332	qpp::Gates, 184		
•	qpp::Gates, 184 RZ		
qpp::QuditDepolarizingNoise, 332	qpp::Gates, 184 RZ qpp::Gates, 184		
qpp::QuditDepolarizingNoise, 332	qpp::Gates, 184 RZ qpp::Gates, 184 S		
qpp::QuditDepolarizingNoise, 332 rand qpp, 91–93	qpp::Gates, 184 RZ qpp::Gates, 184 S qpp::Gates, 187		
qpp::QuditDepolarizingNoise, 332  rand qpp, 91–93 qpp::Dynamic_bitset, 167, 168	qpp::Gates, 184 RZ qpp::Gates, 184 S qpp::Gates, 187 save		
qpp::QuditDepolarizingNoise, 332  rand     qpp, 91–93     qpp::Dynamic_bitset, 167, 168  randH	qpp::Gates, 184 RZ qpp::Gates, 184 S qpp::Gates, 187 save qpp, 103		
qpp::QuditDepolarizingNoise, 332  rand	qpp::Gates, 184 RZ qpp::Gates, 184 S qpp::Gates, 187 save qpp, 103 qpp::RandomDevices, 336		
qpp::QuditDepolarizingNoise, 332  rand     qpp, 91–93     qpp::Dynamic_bitset, 167, 168  randH     qpp, 94  randidx     qpp, 94  randket	qpp::Gates, 184 RZ qpp::Gates, 184 S qpp::Gates, 187 save qpp, 103 qpp::RandomDevices, 336 saveMATLAB qpp, 103, 104 schatten		
qpp::QuditDepolarizingNoise, 332  rand     qpp, 91–93     qpp::Dynamic_bitset, 167, 168  randH     qpp, 94  randidx     qpp, 94	qpp::Gates, 184 RZ qpp::Gates, 184 S qpp::Gates, 187 save qpp, 103 qpp::RandomDevices, 336 saveMATLAB qpp, 103, 104		

schmidtA		qpp::States, 345			
qpp, 105		statistics.h, 405			
schmidtB		stats_			
qpp, 105, 106		qpp::QEngine, 315			
schmidtcoeffs		step_types_			
qpp, 106, 107		qpp::QCircuit, 304			
schmidtprobs		StepType			
qpp, 107, 108		qpp::QCircuit, 277			
separator_	_	storage_size  qpp::Dynamic bitset, 169			
<pre>qpp::internal::IOManipPointer&lt; PointerType     205</pre>	>,	storage_size_			
qpp::internal::IOManipRange< InputIterator	>,	qpp::Dynamic bitset, 170			
208	/,	storage_type			
set		qpp::Dynamic_bitset, 162			
qpp::Dynamic_bitset, 168, 169		subsys_			
set_begin_		qpp::QEngine, 315			
qpp::QCircuit::iterator, 218		sum			
set_dit		qpp, 110, 111			
qpp::QEngine, 313		super2choi			
set_end_		qpp, 111			
qpp::QCircuit::iterator, 218		svals			
set_measured_		qpp, 112			
qpp::QEngine, 313		svd			
set_psi		qpp, 112 svdU			
qpp::QEngine, 314		qpp, 112			
SEVEN_QUBIT_STEANE		svdV			
qpp::Codes, 140		qpp, 113			
sigma qpp, 108		SWAP			
SINGLE		qpp::Bit_circuit, 136			
qpp::QCircuit, 275		qpp::Gates, 187			
SINGLE_cCTRL_MULTIPLE_TARGET		SWAPd			
app::QCircuit, 275		qpp::Gates, 185			
SINGLE_cCTRL_SINGLE_TARGET		syspermute			
qpp::QCircuit, 275		qpp, 113, 114			
SINGLE_CTRL_MULTIPLE_TARGET		Т			
qpp::QCircuit, 275		qpp::Gates, 187			
SINGLE_CTRL_SINGLE_TARGET		target_			
qpp::QCircuit, 275		qpp::QCircuit::GateStep, 191			
Singleton		qpp::QCircuit::MeasureStep, 239			
qpp::internal::Singleton < T >, 338		TFQ			
sinm		qpp, 114			
qpp, 109 size		qpp::QCircuit, 298, 300			
qpp::Dynamic_bitset, 169		THREE			
spectralpowm		qpp::QCircuit, 275			
qpp, 109		qpp::Timer $<$ T, CLOCK T $>$ , 356			
sqrtm		tics			
qpp, 110		qpp::Timer< T, CLOCK_T >, 357			
ST		Timer			
qpp, 31		qpp::Timer< T, CLOCK_T >, 355			
start_		to_JSON			
qpp::internal::IOManipPointer< PointerType	>,	qpp::IJSON, 195			
205		qpp::QCircuit, 300			
qpp::internal::IOManipRange< InputIterator	>,	qpp::QEngine, 314			
208		to_string			
qpp::Timer< T, CLOCK_T >, 357		qpp::Dynamic_bitset, 169			
States		to_void			

qpp,	30		qpp::Gates, 1	85
toc qpp::	Timer< T, CLOCK_T >, 357	Υ		
TOF		vΩ	qpp::Gates, 1	88
	Bit_circuit, 137 Gates, 187	y0	qpp::States, 3	51
trace		y1	ann::Ctataa a	) E 1
qpp, traits.h, 40			qpp::States, 3	101
transpose		Z	qpp::Gates, 1	ឧឧ
qpp, tsallis	115	z0	qppdates, 1	00
	115, 116	z1	qpp::States, 3	51
TWO	QCircuit, 275	Z I	qpp::States, 3	51
Туре	Wolfcult, 270	Zd		٥.
	Codes, 140	zero	qpp::Gates, 1	85
type qpp::	make_void< Ts >, 220		qpp::States, 3	347
type_				
qpp:: types.h, 40	QCircuit::iterator::value_type_, 367 08			
uniform				
qpp,	116			
v_				
qpp:: value_type	Dynamic_bitset, 170			
	Dynamic_bitset, 162			
	QCircuit::iterator, 216			
value_type	e_ QCircuit::iterator::value_type_, 365, 366			
value_type				
	QCircuit::iterator::value_type_, 367			
var qpp,	117			
	ector_emplace			
dbb::	internal, 127			
W				
qpp:: what	States, 350			
	exception::Exception, 175			
what_				
qpp:: where_	exception::CustomException, 144			
	exception::Exception, 176			
Х				
	Bit_circuit, 137			
	Gates, 188			
x0	States, 350			
х1	Ciaico, 500			
	States, 351			
x2contfrac				
Xd Yd				