Quantum++ v1.2

Generated by Doxygen 1.8.14

Contents

1	Qua	ntum++															1
2	Nam	nespace	Index														3
	2.1	Names	space List					 	 	 	 		 	 	 	 	 3
3	Hier	archica	l Index														5
	3.1	Class	Hierarchy					 	 	 	 		 	 	 	 	 5
4	Clas	s Index															7
	4.1	Class	List					 	 	 	 		 	 	 	 	 7
5	File	Index															11
	5.1	File Lis	st					 	 	 	 		 	 	 		 11
6	Nam	nespace	Docume	nta	tion												13
	6.1	qpp Na	amespace	Re	feren	ice .		 	 	 	 		 		 	 	 13
		6.1.1	Detailed	De	scrip	tion		 	 	 	 		 	 	 	 	 26
		6.1.2	Typedef	Dod	cume	entati	on .	 	 	 	 		 	 	 	 	 26
			6.1.2.1	bi	gint			 	 	 	 		 	 	 	 	 26
			6.1.2.2	br	ra .			 	 	 	 		 	 	 	 	 27
			6.1.2.3	cr	mat			 	 	 	 		 		 	 	 27
			6.1.2.4	cp	olx .			 	 	 	 		 	 	 		 27
			6.1.2.5	dr	mat			 	 	 	 		 	 	 	 	 27
			6.1.2.6	dy	yn_c	ol_ve	ect .	 	 	 	 		 		 	 	 27
			6.1.2.7	dy	yn_m	nat .		 	 	 	 		 	 	 	 	 28
			6.1.2.8	d١	vn ro	ow v	ect	 	 	 	 		 	 	 	 	 28

ii CONTENTS

	6.1.2.9	idx	 28
	6.1.2.10	ket	 28
	6.1.2.11	to_void	 28
6.1.3	Enumera	ation Type Documentation	 28
	6.1.3.1	anonymous enum	 28
6.1.4	Function	Documentation	 29
	6.1.4.1	absm()	 29
	6.1.4.2	abssq() [1/3]	 29
	6.1.4.3	abssq() [2/3]	 30
	6.1.4.4	abssq() [3/3]	 30
	6.1.4.5	adjoint()	 30
	6.1.4.6	anticomm()	 31
	6.1.4.7	apply() [1/5]	 31
	6.1.4.8	apply() [2/5]	 32
	6.1.4.9	apply() [3/5]	 32
	6.1.4.10	apply() [4/5]	 33
	6.1.4.11	apply() [5/5]	 33
	6.1.4.12	applyCTRL() [1/2]	 34
	6.1.4.13	applyCTRL() [2/2]	 34
	6.1.4.14	applyQFT()	 35
	6.1.4.15	applyTFQ()	 35
	6.1.4.16	avg()	 36
	6.1.4.17	bloch2rho()	 36
	6.1.4.18	choi2kraus()	 37
	6.1.4.19	choi2super()	 37
	6.1.4.20	comm()	 38
	6.1.4.21	complement()	 38
	6.1.4.22	compperm()	 39
	6.1.4.23	concurrence()	 39
	6.1.4.24	conjugate()	 39

6.1.4.25	contfrac2x()	40
6.1.4.26	convergents() [1/2]	40
6.1.4.27	convergents() [2/2]	41
6.1.4.28	cor()	41
6.1.4.29	cosm()	42
6.1.4.30	cov()	42
6.1.4.31	cwise()	43
6.1.4.32	det()	43
6.1.4.33	dirsum() [1/4]	43
6.1.4.34	dirsum() [2/4]	44
6.1.4.35	dirsum() [3/4]	44
6.1.4.36	dirsum() [4/4]	45
6.1.4.37	dirsumpow()	45
6.1.4.38	disp() [1/5]	46
6.1.4.39	disp() [2/5]	46
6.1.4.40	disp() [3/5]	47
6.1.4.41	disp() [4/5]	47
6.1.4.42	disp() [5/5]	48
6.1.4.43	egcd()	48
6.1.4.44	eig()	49
6.1.4.45	entanglement() [1/2]	49
6.1.4.46	entanglement() [2/2]	50
6.1.4.47	entropy() [1/2]	50
6.1.4.48	entropy() [2/2]	50
6.1.4.49	evals()	51
6.1.4.50	evects()	51
6.1.4.51	expm()	52
6.1.4.52	factors()	52
6.1.4.53	funm()	52
6.1.4.54	gcd() [1/2]	53

iv CONTENTS

6.1.4.55	gcd() [2/2]	53
6.1.4.56	gconcurrence()	54
6.1.4.57	grams() [1/3]	54
6.1.4.58	grams() [2/3]	55
6.1.4.59	grams() [3/3]	55
6.1.4.60	hash_eigen()	56
6.1.4.61	heig()	56
6.1.4.62	hevals()	57
6.1.4.63	hevects()	57
6.1.4.64	inverse()	57
6.1.4.65	invperm()	58
6.1.4.66	ip() [1/2]	58
6.1.4.67	ip() [2/2]	59
6.1.4.68	isprime()	59
6.1.4.69	kraus2choi()	59
6.1.4.70	kraus2super()	60
6.1.4.71	kron() [1/4]	60
6.1.4.72	kron() [2/4]	62
6.1.4.73	kron() [3/4]	62
6.1.4.74	kron() [4/4]	63
6.1.4.75	kronpow()	63
6.1.4.76	lcm() [1/2]	64
6.1.4.77	lcm() [2/2]	64
6.1.4.78	load()	65
6.1.4.79	loadMATLAB() [1/2]	65
6.1.4.80	loadMATLAB() [2/2]	66
6.1.4.81	logdet()	67
6.1.4.82	logm()	67
6.1.4.83	lognegativity() [1/2]	67
6.1.4.84	lognegativity() [2/2]	69

6.1.4.85 marginalX()	69
6.1.4.86 marginalY()	70
6.1.4.87 measure() [1/9]	70
6.1.4.88 measure() [2/9]	70
6.1.4.89 measure() [3/9]	71
6.1.4.90 measure() [4/9]	71
6.1.4.91 measure() [5/9]	72
6.1.4.92 measure() [6/9]	73
6.1.4.93 measure() [7/9]	73
6.1.4.94 measure() [8/9]	74
6.1.4.95 measure() [9/9]	75
6.1.4.96 measure_seq() [1/2]	75
6.1.4.97 measure_seq() [2/2]	76
6.1.4.98 mket() [1/2]	76
6.1.4.99 mket() [2/2]	77
6.1.4.100 modinv()	77
6.1.4.101 modmul()	78
6.1.4.102 modpow()	78
6.1.4.103 mprj() [1/2]	79
6.1.4.104 mprj() [2/2]	79
6.1.4.105 multiidx2n()	80
6.1.4.106 n2multiidx()	80
6.1.4.107 negativity() [1/2]	81
6.1.4.108 negativity() [2/2]	81
6.1.4.109 norm()	82
6.1.4.110 normalize()	82
6.1.4.111 omega()	82
6.1.4.112 powm()	83
6.1.4.113 prj()	83
6.1.4.114 prod() [1/3]	84

vi

6.1.4.115 prod() [2/3]	34
6.1.4.116 prod() [3/3]	34
6.1.4.117 ptrace() [1/2] 8	35
6.1.4.118 ptrace() [2/2] 8	35
6.1.4.119 ptrace1() [1/2] 8	36
6.1.4.120 ptrace1() [2/2] 8	36
6.1.4.121 ptrace2() [1/2] 8	37
6.1.4.122 ptrace2() [2/2] 8	38
6.1.4.123 ptranspose() [1/2]	38
6.1.4.124 ptranspose() [2/2]	39
6.1.4.125 QFT()	39
6.1.4.126 qmutualinfo() [1/2]	39
6.1.4.127 qmutualinfo() [2/2] 9	90
6.1.4.128 rand() [1/5]	90
6.1.4.129 rand() [2/5] 9	91
6.1.4.130 rand() [3/5] 9	91
6.1.4.131 rand() [4/5]	92
6.1.4.132 rand() [5/5] 9	92
6.1.4.133 randH()	93
6.1.4.134 randidx()	93
6.1.4.135 randket()	94
6.1.4.136 randkraus()	94
6.1.4.137 randn() [1/4] 9	94
6.1.4.138 randn() [2/4] 9	95
6.1.4.139 randn() [3/4] 9	95
6.1.4.140 randn() [4/4] 9	96
6.1.4.141 randperm()	96
6.1.4.142 randprime()	97
6.1.4.143 randprob()	97
6.1.4.144 randrho()	97

CONTENTS vii

6.1.4.145 randU()
6.1.4.146 randV()
6.1.4.147 renyi() [1/2]
6.1.4.148 renyi() [2/2]
6.1.4.149 reshape()
6.1.4.150 rho2bloch()
6.1.4.151 rho2pure()
6.1.4.152 save()
6.1.4.153 saveMATLAB() [1/2]
6.1.4.154 saveMATLAB() [2/2]
6.1.4.155 schatten()
6.1.4.156 schmidtA() [1/2]
6.1.4.157 schmidtA() [2/2]
6.1.4.158 schmidtB() [1/2]
6.1.4.159 schmidtB() [2/2]
6.1.4.160 schmidtcoeffs() [1/2]
6.1.4.161 schmidtcoeffs() [2/2]
6.1.4.162 schmidtprobs() [1/2]
6.1.4.163 schmidtprobs() [2/2]
6.1.4.164 sigma()
6.1.4.165 sinm()
6.1.4.166 spectralpowm()
6.1.4.167 sqrtm()
6.1.4.168 sum() [1/3]
6.1.4.169 sum() [2/3]
6.1.4.170 sum() [3/3]
6.1.4.171 super2choi()
6.1.4.172 svals()
6.1.4.173 svd()
6.1.4.174 svdU()

viii CONTENTS

		6.1.4.175	5 svdV()	 111
		6.1.4.176	6 syspermute() [1/2]	 112
		6.1.4.177	7 syspermute() [2/2]	 112
		6.1.4.178	8 TFQ()	 113
		6.1.4.179	9 trace()	 113
		6.1.4.180	0 transpose()	 113
		6.1.4.181	11 tsallis() [1/2]	 114
		6.1.4.182	2 tsallis() [2/2]	 114
		6.1.4.183	3 uniform()	 115
		6.1.4.184	4 var()	 115
		6.1.4.185	5 x2contfrac()	 116
	6.1.5	Variable	Documentation	 116
		6.1.5.1	chop	 116
		6.1.5.2	ee	 116
		6.1.5.3	infty	 116
		6.1.5.4	maxn	 117
		6.1.5.5	pi	 117
6.2	qpp::ex	ception N	Namespace Reference	 117
	6.2.1	Detailed	Description	 118
6.3	qpp::ex	kperimenta	al Namespace Reference	 119
	6.3.1	Detailed	Description	 119
6.4	qpp::in	ternal Nar	mespace Reference	 119
	6.4.1	Detailed	Description	 120
	6.4.2	Function	Documentation	 120
		6.4.2.1	abs_chop() [1/2]	 120
		6.4.2.2	abs_chop() [2/2]	 121
		6.4.2.3	check_cvector()	 121
		6.4.2.4	check_dims()	 121
		6.4.2.5	check_dims_match_cvect()	 121
		6.4.2.6	check_dims_match_mat()	 121

		6.4.2.7	check_dims_match_rvect()	121
		6.4.2.8	check_eq_dims()	122
		6.4.2.9	check_matching_sizes()	122
		6.4.2.10	check_no_duplicates()	122
		6.4.2.11	check_nonzero_size()	122
		6.4.2.12	check_perm()	122
		6.4.2.13	check_qubit_cvector()	122
		6.4.2.14	check_qubit_matrix()	123
		6.4.2.15	check_qubit_rvector()	123
		6.4.2.16	check_qubit_vector()	123
		6.4.2.17	check_rvector()	123
		6.4.2.18	check_square_mat()	123
		6.4.2.19	check_subsys_match_dims()	123
		6.4.2.20	check_vector()	124
		6.4.2.21	dirsum2()	124
		6.4.2.22	get_dim_subsys()	124
		6.4.2.23	get_num_subsys()	124
		6.4.2.24	hash_combine()	124
		6.4.2.25	kron2()	125
		6.4.2.26	multiidx2n()	125
		6.4.2.27	n2multiidx()	125
		6.4.2.28	variadic_vector_emplace() [1/2]	125
		6.4.2.29	variadic_vector_emplace() [2/2]	125
6.5	qpp::lit	erals Nam	espace Reference	126
	6.5.1	Function	Documentation	126
		6.5.1.1	operator""""_bra()	126
		6.5.1.2	operator""""_i() [1/2]	127
		6.5.1.3	operator""""_i() [2/2]	127
		6.5.1.4	operator""""_if() [1/2]	127
		6.5.1.5	operator""""_if() [2/2]	127
		6.5.1.6	operator""""_ket()	127
		6.5.1.7	operator"""" _prj()	128

7	Clas	s Docu	mentation	129
	7.1	qpp::B	t_circuit Class Reference	. 129
		7.1.1	Detailed Description	. 131
		7.1.2	Constructor & Destructor Documentation	. 131
			7.1.2.1 Bit_circuit() [1/2]	. 131
			7.1.2.2 Bit_circuit() [2/2]	. 131
			7.1.2.3 ~Bit_circuit()	. 132
		7.1.3	Member Function Documentation	. 132
			7.1.3.1 CNOT()	. 132
			7.1.3.2 FRED()	. 132
			7.1.3.3 get_gate_count()	. 133
			7.1.3.4 get_gate_depth()	. 133
			7.1.3.5 NOT()	. 134
			7.1.3.6 reset()	. 134
			7.1.3.7 SWAP()	. 134
			7.1.3.8 TOF()	. 135
			7.1.3.9 X()	. 135
		7.1.4	Member Data Documentation	. 136
			7.1.4.1 bCNOT	. 136
			7.1.4.2 bFRED	. 136
			7.1.4.3 bNOT	. 136
			7.1.4.4 bSWAP	. 136
			7.1.4.5 bTOF	. 136
			7.1.4.6 btotal	. 136
			7.1.4.7 count	. 137
			7.1.4.8 depth	. 137
	7.2	qpp::C	odes Class Reference	. 137
		7.2.1	Detailed Description	. 138
		7.2.2	Member Enumeration Documentation	. 138
			7.2.2.1 Type	. 138

CONTENTS xi

	7.2.3	Constructor & Destructor Documentation
		7.2.3.1 Codes()
		7.2.3.2 ~Codes()
	7.2.4	Member Function Documentation
		7.2.4.1 codeword()
	7.2.5	Friends And Related Function Documentation
		7.2.5.1 internal::Singleton < const Codes >
7.3	qpp::ex	xception::CustomException Class Reference
	7.3.1	Detailed Description
	7.3.2	Constructor & Destructor Documentation
		7.3.2.1 CustomException()
	7.3.3	Member Function Documentation
		7.3.3.1 description()
	7.3.4	Member Data Documentation
		7.3.4.1 what
7.4	qpp::ex	xception::DimsInvalid Class Reference
	7.4.1	Detailed Description
	7.4.2	Member Function Documentation
		7.4.2.1 description()
		7.4.2.2 Exception()
7.5	qpp::ex	xception::DimsMismatchCvector Class Reference
	7.5.1	Detailed Description
	7.5.2	Member Function Documentation
		7.5.2.1 description()
		7.5.2.2 Exception()
7.6	qpp::ex	cception::DimsMismatchMatrix Class Reference
	7.6.1	Detailed Description
	7.6.2	Member Function Documentation
		7.6.2.1 description()
		7.6.2.2 Exception()

xii CONTENTS

7.7	qpp::ex	cception::DimsMismatchRvector Class Reference	49
	7.7.1	Detailed Description	50
	7.7.2	Member Function Documentation	50
		7.7.2.1 description()	50
		7.7.2.2 Exception()	50
7.8	qpp::ex	cception::DimsMismatchVector Class Reference	51
	7.8.1	Detailed Description	52
	7.8.2	Member Function Documentation	52
		7.8.2.1 description()	52
		7.8.2.2 Exception()	52
7.9	qpp::ex	cception::DimsNotEqual Class Reference	53
	7.9.1	Detailed Description	54
	7.9.2	Member Function Documentation	54
		7.9.2.1 description()	54
		7.9.2.2 Exception()	54
7.10	qpp::in	ternal::Display_Impl_ Struct Reference	55
	7.10.1	Member Function Documentation	55
		7.10.1.1 display_impl_()	55
7.11	qpp::ex	cception::Duplicates Class Reference	56
	7.11.1	Detailed Description	57
	7.11.2	Member Function Documentation	57
		7.11.2.1 description()	57
		7.11.2.2 Exception()	57
7.12	qpp::D	ynamic_bitset Class Reference	57
	7.12.1	Detailed Description	60
	7.12.2	Member Typedef Documentation	60
		7.12.2.1 storage_type	60
		7.12.2.2 value_type	60
	7.12.3	Constructor & Destructor Documentation	60
		7.12.3.1 Dynamic_bitset()	60

CONTENTS xiii

		7.12.3.2 ~Dynamic_bitset()	161
	7.12.4	Member Function Documentation	161
		7.12.4.1 all()	161
		7.12.4.2 any()	161
		7.12.4.3 count()	161
		7.12.4.4 data()	162
		7.12.4.5 display()	162
		7.12.4.6 flip() [1/2]	162
		7.12.4.7 flip() [2/2]	163
		7.12.4.8 get()	163
		7.12.4.9 index_()	163
		7.12.4.10 none()	164
		7.12.4.11 offset_()	164
		7.12.4.12 operator"!=()	164
		7.12.4.13 operator-()	165
		7.12.4.14 operator==()	165
		7.12.4.15 rand() [1/2]	165
		7.12.4.16 rand() [2/2]	166
		7.12.4.17 reset() [1/2]	166
		7.12.4.18 reset() [2/2]	166
		7.12.4.19 set() [1/2]	167
		7.12.4.20 set() [2/2]	167
		7.12.4.21 size()	167
		7.12.4.22 storage_size()	167
		7.12.4.23 to_string()	168
	7.12.5	Member Data Documentation	168
		7.12.5.1 n	168
		7.12.5.2 storage_size	168
		7.12.5.3 v	169
7.13	qpp::int	ernal::EqualEigen Class Reference	169

xiv CONTENTS

	7.13.1	Detailed Description	39
	7.13.2	Member Function Documentation	39
		7.13.2.1 operator()()	39
7.14	qpp::ex	ception::Exception Class Reference	70
	7.14.1	Detailed Description	71
	7.14.2	Constructor & Destructor Documentation	72
		7.14.2.1 Exception()	72
	7.14.3	Member Function Documentation	72
		7.14.3.1 description()	72
		7.14.3.2 what()	73
	7.14.4	Member Data Documentation	73
		7.14.4.1 msg	73
		7.14.4.2 where	73
7.15	qpp::Ga	ates Class Reference	73
	7.15.1	Detailed Description	⁷ 6
	7.15.2	Constructor & Destructor Documentation	⁷ 6
		7.15.2.1 Gates()	⁷ 6
		7.15.2.2 ~Gates()	⁷ 6
	7.15.3	Member Function Documentation	⁷ 6
		7.15.3.1 CTRL()	⁷ 6
		7.15.3.2 expandout() [1/3]	77
		7.15.3.3 expandout() [2/3]	7
		7.15.3.4 expandout() [3/3]	78
		7.15.3.5 Fd()	79
		7.15.3.6 get_name()	79
		7.15.3.7 ld()	30
		7.15.3.8 MODMUL()	30
		7.15.3.9 Rn()	31
		7.15.3.10 RX()	31
		7.15.3.11 RY()	31

CONTENTS xv

		7.15.3.12 RZ()	32
		7.15.3.13 SWAPd()	32
		7.15.3.14 Xd()	32
		7.15.3.15 Zd()	33
	7.15.4	Friends And Related Function Documentation	33
		7.15.4.1 internal::Singleton < const Gates >	33
	7.15.5	Member Data Documentation	33
		7.15.5.1 CNOT	33
		7.15.5.2 CNOTba	34
		7.15.5.3 CZ	34
		7.15.5.4 FRED	34
		7.15.5.5 H	34
		7.15.5.6 ld2	34
		7.15.5.7 S	34
		7.15.5.8 SWAP	35
		7.15.5.9 T	35
		7.15.5.10 TOF	35
		7.15.5.11 X	35
		7.15.5.12 Y	35
		7.15.5.13 Z	35
7.16	qpp::Q0	Circuit::GateStep Struct Reference	36
	7.16.1	Detailed Description	37
	7.16.2	Constructor & Destructor Documentation	37
		7.16.2.1 GateStep() [1/2]	37
		7.16.2.2 GateStep() [2/2]	37
	7.16.3	Member Data Documentation	37
		7.16.3.1 ctrl	37
		7.16.3.2 gate_hash	38
		7.16.3.3 gate_type	38
		7.16.3.4 name	38

xvi CONTENTS

		7.16.3.5 target	188
7.17	qpp::int	ternal::HashEigen Class Reference	188
	7.17.1	Detailed Description	189
	7.17.2	Member Function Documentation	189
		7.17.2.1 operator()()	189
7.18	qpp::ID	Display Class Reference	189
	7.18.1	Detailed Description	190
	7.18.2	Constructor & Destructor Documentation	190
		7.18.2.1 ~IDisplay()	190
	7.18.3	Member Function Documentation	190
		7.18.3.1 display()	190
	7.18.4	Friends And Related Function Documentation	191
		7.18.4.1 operator<<	191
7.19	qpp::IJ	SON Class Reference	191
	7.19.1	Detailed Description	192
	7.19.2	Constructor & Destructor Documentation	192
		7.19.2.1 ~IJSON()	192
	7.19.3	Member Function Documentation	192
		7.19.3.1 to_JSON()	192
7.20	qpp::Ini	it Class Reference	192
	7.20.1	Detailed Description	193
	7.20.2	Constructor & Destructor Documentation	194
		7.20.2.1 Init()	194
		7.20.2.2 ~Init()	194
	7.20.3	Friends And Related Function Documentation	194
		7.20.3.1 internal::Singleton < const Init >	194
7.21	qpp::ex	cception::InvalidIterator Class Reference	194
	7.21.1	Detailed Description	196
	7.21.2	Member Function Documentation	196
		7.21.2.1 description()	196

CONTENTS xvii

		7.21.2.2 Exception()	96
7.22	qpp::int	ernal::IOManipEigen Class Reference	96
	7.22.1	Constructor & Destructor Documentation	98
		7.22.1.1 IOManipEigen() [1/2]	98
		7.22.1.2 IOManipEigen() [2/2]	98
	7.22.2	Member Function Documentation	98
		7.22.2.1 display()	98
	7.22.3	Member Data Documentation	98
		7.22.3.1 A	98
		7.22.3.2 chop	99
7.23	qpp::int	ernal::IOManipPointer< PointerType > Class Template Reference	99
	7.23.1	Constructor & Destructor Documentation	200
		7.23.1.1 IOManipPointer() [1/2]	200
		7.23.1.2 IOManipPointer() [2/2]	200
	7.23.2	Member Function Documentation	200
		7.23.2.1 display()	201
		7.23.2.2 operator=()	201
	7.23.3	Member Data Documentation	201
		7.23.3.1 chop	201
		7.23.3.2 end	201
		7.23.3.3 N	201
		7.23.3.4 p	202
		7.23.3.5 separator	202
		7.23.3.6 start	202
7.24	qpp::int	ernal::IOManipRange< InputIterator > Class Template Reference	202
	7.24.1	Constructor & Destructor Documentation	203
		7.24.1.1 IOManipRange() [1/2]	204
		7.24.1.2 IOManipRange() [2/2]	204
	7.24.2	Member Function Documentation	204
		7.24.2.1 display()	204

xviii CONTENTS

		7.24.2.2 operator=()	204
	7.24.3	Member Data Documentation	204
		7.24.3.1 chop	205
		7.24.3.2 end	205
		7.24.3.3 first	205
		7.24.3.4 last	205
		7.24.3.5 separator	205
		7.24.3.6 start	205
7.25	qpp::is_	_complex< T > Struct Template Reference	206
	7.25.1	Detailed Description	206
7.26	qpp::is_	_complex< std::complex< T > > Struct Template Reference	207
	7.26.1	Detailed Description	207
7.27	qpp::is_	_iterable < T, typename > Struct Template Reference	208
	7.27.1	Detailed Description	208
7.28		_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T d()), decltype(*(std::declval < T >().begin())) > Struct Template Reference	209
	7.28.1	Detailed Description	210
7.29	qpp::is_	_matrix_expression< Derived > Struct Template Reference	210
	7 20 1		
	7.29.1	Detailed Description	210
7.30		Detailed Description	
7.30	qpp::Q	•	211
7.30	qpp::Q0	Circuit::iterator Class Reference	211 212
7.30	qpp::Q0	Circuit::iterator Class Reference	211 212 212
7.30	qpp::Q0	Circuit::iterator Class Reference	211 212 212 212
7.30	qpp::Q0	Circuit::iterator Class Reference	211 212 212 212 212
7.30	qpp::Q0	Circuit::iterator Class Reference	211 212 212 212 212 213
7.30	qpp::Q0	Circuit::iterator Class Reference	211 212 212 212 212 213 213
7.30	qpp::Q0 7.30.1 7.30.2	Circuit::iterator Class Reference Detailed Description Member Typedef Documentation 7.30.2.1 difference_type 7.30.2.2 iterator_category 7.30.2.3 pointer 7.30.2.4 reference	211 212 212 212 212 213 213 213
7.30	qpp::Q0 7.30.1 7.30.2	Circuit::iterator Class Reference Detailed Description Member Typedef Documentation 7.30.2.1 difference_type 7.30.2.2 iterator_category 7.30.2.3 pointer 7.30.2.4 reference 7.30.2.5 value_type	211 212 212 212 212 213 213 213
7.30	qpp::Q0 7.30.1 7.30.2	Circuit::iterator Class Reference Detailed Description Member Typedef Documentation 7.30.2.1 difference_type 7.30.2.2 iterator_category 7.30.2.3 pointer 7.30.2.4 reference 7.30.2.5 value_type Constructor & Destructor Documentation	211 212 212 212 213 213 213 213 213

CONTENTS xix

		7.30.4.1 operator"!=()
		7.30.4.2 operator*()
		7.30.4.3 operator++() [1/2]
		7.30.4.4 operator++() [2/2]
		7.30.4.5 operator=()
		7.30.4.6 operator==()
		7.30.4.7 set_begin_()
		7.30.4.8 set_end_()
	7.30.5	Member Data Documentation
		7.30.5.1 elem
		7.30.5.2 qc
7.31	qpp::ma	ake_void < Ts > Struct Template Reference
	7.31.1	Detailed Description
	7.31.2	Member Typedef Documentation
		7.31.2.1 type
7.32	qpp::ex	ception::MatrixMismatchSubsys Class Reference
	7.32.1	Detailed Description
	7.32.2	Member Function Documentation
		7.32.2.1 description()
		7.32.2.2 Exception()
7.33	qpp::ex	ception::MatrixNotCvector Class Reference
	7.33.1	Detailed Description
	7.33.2	Member Function Documentation
		7.33.2.1 description()
		7.33.2.2 Exception()
7.34	qpp::ex	ception::MatrixNotRvector Class Reference
	7.34.1	Detailed Description
	7.34.2	Member Function Documentation
		7.34.2.1 description()
		7.5 T.Z. Good planty

7.35	qpp::ex	cception::MatrixNotSquare Class Reference	223
	7.35.1	Detailed Description	225
	7.35.2	Member Function Documentation	225
		7.35.2.1 description()	225
		7.35.2.2 Exception()	225
7.36	qpp::ex	cception::MatrixNotSquareNorCvector Class Reference	225
	7.36.1	Detailed Description	227
	7.36.2	Member Function Documentation	227
		7.36.2.1 description()	227
		7.36.2.2 Exception()	227
7.37	qpp::ex	cception::MatrixNotSquareNorRvector Class Reference	227
	7.37.1	Detailed Description	229
	7.37.2	Member Function Documentation	229
		7.37.2.1 description()	229
		7.37.2.2 Exception()	229
7.38	qpp::ex	cception::MatrixNotSquareNorVector Class Reference	229
	7.38.1	Detailed Description	231
	7.38.2	Member Function Documentation	231
		7.38.2.1 description()	231
		7.38.2.2 Exception()	231
7.39	qpp::ex	cception::MatrixNotVector Class Reference	231
	7.39.1	Detailed Description	233
	7.39.2	Member Function Documentation	233
		7.39.2.1 description()	233
		7.39.2.2 Exception()	233
7.40	qpp::Q	Circuit::MeasureStep Struct Reference	233
	7.40.1	Detailed Description	234
	7.40.2	Constructor & Destructor Documentation	234
		7.40.2.1 MeasureStep() [1/2]	235
		7.40.2.2 MeasureStep() [2/2]	235

CONTENTS xxi

	7.40.3	Member Data Documentation
		7.40.3.1 c_reg
		7.40.3.2 mats_hash
		7.40.3.3 measurement_type
		7.40.3.4 name
		7.40.3.5 target
7.41	qpp::ex	cception::NoCodeword Class Reference
	7.41.1	Detailed Description
	7.41.2	Member Function Documentation
		7.41.2.1 description()
		7.41.2.2 Exception()
7.42	qpp::No	piseBase < T > Class Template Reference
	7.42.1	Detailed Description
	7.42.2	Member Typedef Documentation
		7.42.2.1 noise_type
	7.42.3	Constructor & Destructor Documentation
		7.42.3.1 NoiseBase() [1/2]
		7.42.3.2 NoiseBase() [2/2]
		7.42.3.3 ~NoiseBase()
	7.42.4	Member Function Documentation
		7.42.4.1 compute_probs_()
		7.42.4.2 compute_state_()
		7.42.4.3 get_d()
		7.42.4.4 get_Ks()
		7.42.4.5 get_last_idx()
		7.42.4.6 get_last_K()
		7.42.4.7 get_last_p()
		7.42.4.8 get_probs()
		7.42.4.9 operator()() [1/3]
		7.42.4.10 operator()() [2/3]

xxii CONTENTS

7.42.4.11 operator()() [3/3]	244
7.42.5 Member Data Documentation	245
7.42.5.1 d	245
7.42.5.2 generated	245
7.42.5.3 i	245
7.42.5.4 Ks	245
7.42.5.5 probs	246
7.43 qpp::NoiseType Class Reference	246
7.43.1 Detailed Description	246
7.44 qpp::exception::NotBipartite Class Reference	246
7.44.1 Detailed Description	248
7.44.2 Member Function Documentation	248
7.44.2.1 description()	248
7.44.2.2 Exception()	248
7.45 qpp::exception::NotImplemented Class Reference	248
7.45.1 Detailed Description	
7.45.2 Member Function Documentation	
7.45.2.1 description()	
7.45.2.2 Exception()	
7.46 qpp::exception::NotQubitCvector Class Reference	
7.46.1 Detailed Description	
7.46.2 Member Function Documentation	
7.46.2.1 description()	
7.46.2.2 Exception()	
7.47 qpp::exception::NotQubitMatrix Class Reference	
7.47.1 Detailed Description	
7.47.2 Member Function Documentation	254
7.47.2.1 description()	
7.47.2.2 Exception()	
7.48 qpp::exception::NotQubitRvector Class Reference	

CONTENTS xxiii

	7.48.1	Detailed Description	56
	7.48.2	Member Function Documentation	56
		7.48.2.1 description()	56
		7.48.2.2 Exception()	56
7.49	qpp::ex	cception::NotQubitSubsys Class Reference	56
	7.49.1	Detailed Description	58
	7.49.2	Member Function Documentation	58
		7.49.2.1 description()	58
		7.49.2.2 Exception()	58
7.50	qpp::ex	cception::NotQubitVector Class Reference	58
	7.50.1	Detailed Description	30
	7.50.2	Member Function Documentation	30
		7.50.2.1 description()	30
		7.50.2.2 Exception()	60
7.51	qpp::ex	cception::OutOfRange Class Reference	60
	7.51.1	Detailed Description	62
	7.51.2	Member Function Documentation	62
		7.51.2.1 description()	32
		7.51.2.2 Exception()	62
7.52	qpp::ex	cception::PermInvalid Class Reference	62
	7.52.1	Detailed Description	64
	7.52.2	Member Function Documentation	64
		7.52.2.1 description()	64
		7.52.2.2 Exception()	64
7.53	qpp::ex	cception::PermMismatchDims Class Reference	64
	7.53.1	Detailed Description	36
	7.53.2	Member Function Documentation	36
		7.53.2.1 description()	36
		7.53.2.2 Exception()	36
7.54	qpp::Q	Circuit Class Reference	37

xxiv CONTENTS

7.54.1	Detailed Description
7.54.2	Member Typedef Documentation
	7.54.2.1 const_iterator
7.54.3	Member Enumeration Documentation
	7.54.3.1 GateType
	7.54.3.2 MeasureType
	7.54.3.3 StepType
7.54.4	Constructor & Destructor Documentation
	7.54.4.1 QCircuit()
	7.54.4.2 ~QCircuit()
7.54.5	Member Function Documentation
	7.54.5.1 add_dit()
	7.54.5.2 add_hash_()
	7.54.5.3 add_qudit()
	7.54.5.4 begin() [1/2]
	7.54.5.5 begin() [2/2]
	7.54.5.6 cbegin()
	7.54.5.7 cCTRL() [1/4]
	7.54.5.8 cCTRL() [2/4]
	7.54.5.9 cCTRL() [3/4]
	7.54.5.10 cCTRL() [4/4]
	7.54.5.11 cCTRL_custom()
	7.54.5.12 cend()
	7.54.5.13 CTRL() [1/4]
	7.54.5.14 CTRL() [2/4]
	7.54.5.15 CTRL() [3/4]
	7.54.5.16 CTRL() [4/4]
	7.54.5.17 CTRL_custom()
	7.54.5.18 display()
	7.54.5.19 end() [1/2]

CONTENTS xxv

7.54.5.20 end() [2/2]
7.54.5.22 gate() [2/3]
7.54.5.23 gate() [3/3]
7.54.5.24 gate_custom()
7.54.5.25 gate_fan() [1/3]
7.54.5.26 gate_fan() [2/3]
7.54.5.27 gate_fan() [3/3]
7.54.5.28 get_cmat_hash_tbl_()
7.54.5.29 get_d()
7.54.5.30 get_gate_count()
7.54.5.31 get_gate_depth()
7.54.5.32 get_gates_()
7.54.5.33 get_measured() [1/2]
7.54.5.34 get_measured() [2/2]
7.54.5.35 get_measurement_count() [1/2]
7.54.5.36 get_measurement_count() [2/2]
7.54.5.37 get_measurements_()
7.54.5.38 get_name()
7.54.5.39 get_nc()
7.54.5.40 get_non_measured()
7.54.5.41 get_nop_count()
7.54.5.42 get_nq()
7.54.5.43 get_step_count()
7.54.5.44 measureV() [1/2]
7.54.5.45 measureV() [2/2]
7.54.5.46 measureZ()
7.54.5.47 nop()
7.54.5.48 QFT() [1/3]
7.54.5.49 QFT() [2/3]

xxvi CONTENTS

	7.54.5.50 QFT() [3/3]	291
	7.54.5.51 TFQ() [1/3]	292
	7.54.5.52 TFQ() [2/3]	292
	7.54.5.53 TFQ() [3/3]	292
	7.54.5.54 to_JSON()	293
7.54.6	Friends And Related Function Documentation	293
	7.54.6.1 operator<< [1/4]	293
	7.54.6.2 operator<< [2/4]	294
	7.54.6.3 operator << [3/4]	294
	7.54.6.4 operator<< [4/4]	294
	7.54.6.5 QEngine	295
7.54.7	Member Data Documentation	295
	7.54.7.1 cmat_hash_tbl	295
	7.54.7.2 count	295
	7.54.7.3 d	295
	7.54.7.4 gates	295
	7.54.7.5 measured	296
	7.54.7.6 measurement_count	296
	7.54.7.7 measurements	296
	7.54.7.8 name	296
	7.54.7.9 nc	296
	7.54.7.10 nq	296
	7.54.7.11 step_types	297
7.55 qpp::Q	Engine Class Reference	297
7.55.1	Detailed Description	299
7.55.2	Constructor & Destructor Documentation	299
	7.55.2.1 QEngine() [1/3]	299
	7.55.2.2 QEngine() [2/3]	300
	7.55.2.3 QEngine() [3/3]	300
	7.55.2.4 ~QEngine()	300

CONTENTS xxvii

	7.55.3	Member Function Documentation
		7.55.3.1 display()
		7.55.3.2 execute() [1/3]
		7.55.3.3 execute() [2/3]
		7.55.3.4 execute() [3/3]
		7.55.3.5 get_circuit()
		7.55.3.6 get_dit()
		7.55.3.7 get_dits()
		7.55.3.8 get_measured() [1/2]
		7.55.3.9 get_measured() [2/2]
		7.55.3.10 get_non_measured()
		7.55.3.11 get_probs()
		7.55.3.12 get_psi()
		7.55.3.13 get_relative_pos_()
		7.55.3.14 operator=()
		7.55.3.15 reset()
		7.55.3.16 set_dit()
		7.55.3.17 set_measured_()
		7.55.3.18 set_psi()
		7.55.3.19 to_JSON()
	7.55.4	Member Data Documentation
		7.55.4.1 dits
		7.55.4.2 probs
		7.55.4.3 psi
		7.55.4.4 qc
		7.55.4.5 subsys
7.56	qpp::Ql	NoisyEngine < NoiseModel > Class Template Reference
	7.56.1	Detailed Description
	7.56.2	Constructor & Destructor Documentation
		7.56.2.1 QNoisyEngine()

xxviii CONTENTS

	7.56.3	Member Function Documentation
		7.56.3.1 execute() [1/4] 31
		7.56.3.2 execute() [2/4] 31
		7.56.3.3 execute() [3/4]
		7.56.3.4 execute() [4/4]
		7.56.3.5 get_noise_results()
	7.56.4	Member Data Documentation
		7.56.4.1 noise
		7.56.4.2 noise_results
7.57	qpp::Q	ubitAmplitudeDampingNoise Class Reference
	7.57.1	Detailed Description
	7.57.2	Constructor & Destructor Documentation
		7.57.2.1 QubitAmplitudeDampingNoise()
7.58	qpp::Q	ubitBitFlipNoise Class Reference
	7.58.1	Detailed Description
	7.58.2	Constructor & Destructor Documentation
		7.58.2.1 QubitBitFlipNoise()
7.59	qpp::Q	ubitBitPhaseFlipNoise Class Reference
	7.59.1	Detailed Description
	7.59.2	Constructor & Destructor Documentation
		7.59.2.1 QubitBitPhaseFlipNoise()
7.60	qpp::Q	ubitDepolarizingNoise Class Reference
	7.60.1	Detailed Description
	7.60.2	Constructor & Destructor Documentation
		7.60.2.1 QubitDepolarizingNoise()
7.61	qpp::Q	ubitPhaseDampingNoise Class Reference
	7.61.1	Detailed Description
	7.61.2	Constructor & Destructor Documentation
		7.61.2.1 QubitPhaseDampingNoise()
7.62	qpp::Q	ubitPhaseFlipNoise Class Reference

CONTENTS xxix

	7.62.1	Detailed Description	321
	7.62.2	Constructor & Destructor Documentation	321
		7.62.2.1 QubitPhaseFlipNoise()	321
7.63	qpp::ex	cception::QuditAlreadyMeasured Class Reference	321
	7.63.1	Detailed Description	322
	7.63.2	Member Function Documentation	322
		7.63.2.1 description()	323
		7.63.2.2 Exception()	323
7.64	qpp::Q	uditDepolarizingNoise Class Reference	323
	7.64.1	Detailed Description	324
	7.64.2	Constructor & Destructor Documentation	324
		7.64.2.1 QuditDepolarizingNoise()	324
	7.64.3	Member Function Documentation	325
		7.64.3.1 fill_Ks_()	325
		7.64.3.2 fill_probs_()	325
7.65	qpp::Ra	andomDevices Class Reference	326
	7.65.1	Detailed Description	327
	7.65.2	Constructor & Destructor Documentation	327
		7.65.2.1 RandomDevices()	327
		7.65.2.2 ~RandomDevices()	328
	7.65.3	Member Function Documentation	328
		7.65.3.1 get_prng()	328
		7.65.3.2 load()	328
		7.65.3.3 save()	328
	7.65.4	Friends And Related Function Documentation	329
		7.65.4.1 internal::Singleton < RandomDevices >	329
	7.65.5	Member Data Documentation	329
		7.65.5.1 prng	329
		7.65.5.2 rd	329
7.66	qpp::int	ternal::Singleton< T > Class Template Reference	329

	7.66.1	Detailed Description	330
	7.66.2	Constructor & Destructor Documentation	330
		7.66.2.1 Singleton() [1/2]	331
		7.66.2.2 Singleton() [2/2]	331
		7.66.2.3 ~Singleton()	331
	7.66.3	Member Function Documentation	331
		7.66.3.1 get_instance()	331
		7.66.3.2 get_thread_local_instance()	331
		7.66.3.3 operator=()	331
7.67	qpp::ex	ception::SizeMismatch Class Reference	332
	7.67.1	Detailed Description	333
	7.67.2	Member Function Documentation	333
		7.67.2.1 description()	333
		7.67.2.2 Exception()	333
7.68	qpp::No	piseType::StateDependent Class Reference	334
	7.68.1	Detailed Description	334
7.69	qpp::No	piseType::StateIndependent Class Reference	334
	7.69.1	Detailed Description	334
7.70	qpp::St	ates Class Reference	334
	7.70.1	Detailed Description	336
	7.70.2	Constructor & Destructor Documentation	337
		7.70.2.1 States()	337
		7.70.2.2 ~States()	337
	7.70.3	Member Function Documentation	337
		7.70.3.1 jn()	337
		7.70.3.2 mes()	337
		7.70.3.3 minus()	338
		7.70.3.4 one()	338
		7.70.3.5 plus()	339
		7.70.3.6 zero()	339

CONTENTS xxxi

7.70.4	Friends And Related Function Documentation	39
	7.70.4.1 internal::Singleton < const States >	39
7.70.5	Member Data Documentation	39
	7.70.5.1 b00	40
	7.70.5.2 b01	40
	7.70.5.3 b10	40
	⁷ .70.5.4 b11	40
	⁷ .70.5.5 GHZ	40
	7.70.5.6 pb00	40
	⁷ .70.5.7 pb01	41
	7.70.5.8 pb10	41
	⁷ .70.5.9 pb11	41
	⁷ .70.5.10 pGHZ	41
	⁷ .70.5.11 pW	41
	7.70.5.12 px0	41
	⁷ .70.5.13 px1	42
	⁷ .70.5.14 py0	42
	⁷ .70.5.15 py1	42
	7.70.5.16 pz0	42
	⁷ .70.5.17 pz1	42
	7.70.5.18 W	42
	7.70.5.19 x0	43
	⁷ .70.5.20 x1	43
	7.70.5.21 y0	43
	⁷ .70.5.22 y1	43
	7.70.5.23 z0	43
	7.70.5.24 z1	43
qpp::ex	eption::SubsysMismatchDims Class Reference	44
7.71.1	Detailed Description	45
7.71.2	Member Function Documentation	45

7.71

xxxii CONTENTS

	7.71.2.1 description()	45
	7.71.2.2 Exception()	45
7.72 qpp::Ti	mer< T, CLOCK_T > Class Template Reference	46
7.72.1	Detailed Description	47
7.72.2	Constructor & Destructor Documentation	47
	7.72.2.1 Timer()	47
	7.72.2.2 ~Timer()	47
7.72.3	Member Function Documentation	48
	7.72.3.1 display()	48
	7.72.3.2 get_duration()	48
	7.72.3.3 tic()	49
	7.72.3.4 tics()	49
	7.72.3.5 toc()	49
7.72.4	Member Data Documentation	49
	7.72.4.1 end	49
	7.72.4.2 start	50
7.73 qpp::ex	ception::TypeMismatch Class Reference	50
7.73.1	Detailed Description	51
7.73.2	Member Function Documentation	51
	7.73.2.1 description()	51
	7.73.2.2 Exception()	52
7.74 qpp::ex	ception::UndefinedType Class Reference	52
7.74.1	Detailed Description	53
7.74.2	Member Function Documentation	53
	7.74.2.1 description()	53
	7.74.2.2 Exception()	54
7.75 qpp::ex	ception::Unknown Class Reference	54
7.75.1	Detailed Description	55
7.75.2	Member Function Documentation	55
	7.75.2.1 description()	55

CONTENTS xxxiii

		7.75.2.2	Exception() .				 	 	 	 		356
7.76	qpp::Q	Circuit::iter	ator::value_typ	oe_ Class	Referer	nce .	 	 	 	 		356
	7.76.1	Detailed D	Description .				 	 	 	 		357
	7.76.2	Construct	or & Destructo	or Docume	ntation		 	 	 	 		357
		7.76.2.1	value_type_()) [1/2] .			 	 	 	 		357
		7.76.2.2	value_type_()) [2/2] .			 	 	 	 		358
	7.76.3	Member F	Function Docu	mentation			 	 	 	 		358
		7.76.3.1	display()				 	 	 	 		358
		7.76.3.2	operator=() .				 	 	 	 		358
	7.76.4	Member [Data Documer	ntation			 	 	 	 		358
		7.76.4.1	gates_ip				 	 	 	 		359
		7.76.4.2	ip				 	 	 	 		359
		7.76.4.3	measuremen	ts_ip			 	 	 	 		359
		7.76.4.4	type				 	 	 	 		359
		7.76.4.5	value_type_q	C			 	 	 	 		359
7.77	qpp::ex	ception::Ze	eroSize Class	Reference			 	 	 	 		360
	7.77.1	Detailed D	Description .				 	 	 	 		361
	7.77.2	Member F	Function Docu	mentation			 	 	 	 		361
		7.77.2.1	description()				 	 	 	 		361
		7.77.2.2	Exception() .				 	 	 	 		361

8	File I	Documentation	363
	8.1	classes/circuits/circuits.h File Reference	363
		8.1.1 Detailed Description	364
	8.2	classes/circuits/engines.h File Reference	364
		8.2.1 Detailed Description	364
	8.3	classes/codes.h File Reference	365
		8.3.1 Detailed Description	365
	8.4	classes/exception.h File Reference	365
		8.4.1 Detailed Description	367
	8.5	classes/gates.h File Reference	367
		8.5.1 Detailed Description	368
	8.6	classes/idisplay.h File Reference	368
		8.6.1 Detailed Description	369
	8.7	classes/init.h File Reference	369
		8.7.1 Detailed Description	369
	8.8	classes/noise.h File Reference	370
		8.8.1 Detailed Description	370
	8.9	classes/random_devices.h File Reference	371
		8.9.1 Detailed Description	371
	8.10	classes/reversible.h File Reference	371
		8.10.1 Detailed Description	372
	8.11	classes/states.h File Reference	372
		8.11.1 Detailed Description	373
	8.12	classes/timer.h File Reference	373
		8.12.1 Detailed Description	373
	8.13	constants.h File Reference	374
		8.13.1 Detailed Description	375
	8.14	entanglement.h File Reference	375
		8.14.1 Detailed Description	377
	8.15	entropies.h File Reference	377

CONTENTS XXXV

	8.15.1 Detailed Description	378
8.16	experimental/experimental.h File Reference	378
	8.16.1 Detailed Description	378
8.17	functions.h File Reference	378
	8.17.1 Detailed Description	383
8.18	input_output.h File Reference	383
	8.18.1 Detailed Description	384
8.19	instruments.h File Reference	384
	8.19.1 Detailed Description	386
8.20	internal/classes/iomanip.h File Reference	386
	8.20.1 Detailed Description	386
8.21	internal/classes/singleton.h File Reference	387
	8.21.1 Detailed Description	387
8.22	internal/util.h File Reference	387
	8.22.1 Detailed Description	389
8.23	MATLAB/matlab.h File Reference	389
	8.23.1 Detailed Description	390
8.24	number_theory.h File Reference	390
	8.24.1 Detailed Description	391
8.25	operations.h File Reference	392
	8.25.1 Detailed Description	394
8.26	qpp.h File Reference	394
	8.26.1 Detailed Description	395
	8.26.2 Macro Definition Documentation	395
	8.26.2.1 QPP_UNUSED	395
8.27	random.h File Reference	396
	8.27.1 Detailed Description	397
8.28	statistics.h File Reference	397
	8.28.1 Detailed Description	398
8.29	traits.h File Reference	398
	8.29.1 Detailed Description	399
8.30	types.h File Reference	400
	8.30.1 Detailed Description	400
Index		401

Chapter 1

Quantum++

Version 1.2 - 10 February 2019

Build status:

Chat (questions/issues)

About

Quantum++ is a modern C++11 general purpose quantum computing library, composed solely of template header files. Quantum++ is written in standard C++11 and has very low external dependencies, using only the Eigen 3 linear algebra header-only template library and, if available, the OpenMP multi-processing library.

Quantum++ is not restricted to qubit systems or specific quantum information processing tasks, being capable of simulating arbitrary quantum processes. The main design factors taken in consideration were the ease of use, high portability, and high performance. The library's simulation capabilities are only restricted by the amount of available physical memory. On a typical machine (Intel i5 8Gb RAM) Quantum++ can successfully simulate the evolution of 25 qubits in a pure state or of 12 qubits in a mixed state reasonably fast.

To report any bugs or ask for additional features/enhancements, please submit an issue with an appropriate label.

If you are interesting in contributing to this project, feel free to contact me. Alternatively, create a custom branch, add your contribution, then finally create a pull request. If I accept the pull request, I will merge your custom branch with the latest development branch. The latter will eventually be merged into a future release version. To contribute, you need to have a solid knowledge of C++ (preferably C++11), including templates and the standard library, a basic knowledge of quantum computing and linear algebra, and working experience with Eigen 3.

For additional Eigen 3 documentation see http://eigen.tuxfamily.org/dox/. For a simple Eigen 3 quick ASCII reference see http://eigen.tuxfamily.org/dox/AsciiQuickReference.txt.

Copyright (c) 2013 - 2019 Vlad Gheorghiu, vgheorgh AT gmail DOT com.

License

Quantum++ is distributed under the MIT license. Please see the LICENSE file for more details.

Installation instructions and further documentation

Please see the installation guide https://github.com/vsoftco/qpp/blob/master/INSTALL.md "`INSTALL.md`" and the comprehensive Wiki for further documentation and detailed examples.

The official API documentation is available in PDF and HTML formats in the doc folder.

2 Quantum++

Chapter 2

Namespace Index

2.1 Namespace List

Here is a list of all namespaces with brief descriptions:

op
Quantum++ main namespace
pp::exception
Quantum++ exception hierarchy namespace
pp::experimental
Experimental/test functions/classes, do not use or modify
op::internal
Internal utility functions, do not use them directly or modify them
pp::literals

4 Namespace Index

Chapter 3

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

qpp::internal::Display_Impl
qpp::internal::IOManipEigen
qpp::internal::EqualEigen
std::exception
qpp::exception::Exception
qpp::exception::CustomException
qpp::exception::DimsInvalid
qpp::exception::DimsMismatchCvector
qpp::exception::DimsMismatchMatrix
qpp::exception::DimsMismatchRvector
qpp::exception::DimsMismatchVector
qpp::exception::DimsNotEqual
qpp::exception::Duplicates
qpp::exception::InvalidIterator
qpp::exception::MatrixMismatchSubsys
qpp::exception::MatrixNotCvector
qpp::exception::MatrixNotRvector
qpp::exception::MatrixNotSquare
qpp::exception::MatrixNotSquareNorCvector
qpp::exception::MatrixNotSquareNorRvector
qpp::exception::MatrixNotSquareNorVector
qpp::exception::MatrixNotVector
qpp::exception::NoCodeword
qpp::exception::NotBipartite
qpp::exception::NotImplemented
qpp::exception::NotQubitCvector
qpp::exception::NotQubitMatrix
qpp::exception::NotQubitRvector
qpp::exception::NotQubitSubsys
qpp::exception::NotQubitVector
qpp::exception::OutOfRange
qpp::exception::PermInvalid
qpp::exception::PermMismatchDims
qpp::exception::QuditAlreadyMeasured
gpp::exception::SizeMismatch

6 Hierarchical Index

qpp::exception::SubsysMismatchDims	. 344
qpp::exception::TypeMismatch	
<pre>qpp::exception::UndefinedType</pre>	
app::exception::Unknown	. 354
qpp::exception::ZeroSize	
false type	
	. 206
<pre>qpp::is_iterable < T, typename ></pre>	
qpp::QCircuit::GateStep	
qpp::internal::HashEigen	
qpp::IDisplay	
qpp::Dynamic_bitset	
qpp::Bit circuit	
qpp::internal::IOManipEigen	
qpp::internal::IOManipPointer< PointerType >	

qpp::internal::IOManipRange< InputIterator >	
qpp::QCircuit	
qpp::QCircuit::iterator::value_type	
qpp::QEngine	
qpp::QNoisyEngine < NoiseModel >	
qpp::Timer< T, CLOCK_T >	
qpp::IJSON	191
qpp::QCircuit	. 267
qpp::QEngine	. 297
is_base_of	
qpp::is_matrix_expression< Derived >	. 210
qpp::QCircuit::iterator	
<pre>qpp::make_void < Ts ></pre>	
qpp::QCircuit::MeasureStep	
qpp::NoiseBase< T >	
qpp::NoiseBase < NoiseType::StateDependent >	
qpp::QubitAmplitudeDampingNoise	
qpp::QubitPhaseDampingNoise	
" · ·	
qpp::NoiseBase< NoiseType::StateIndependent >	
qpp::QubitBitFlipNoise	
qpp::QubitBitPhaseFlipNoise	
qpp::QubitDepolarizingNoise	
qpp::QubitPhaseFlipNoise	
qpp::QuditDepolarizingNoise	
qpp::NoiseType	246
$qpp::internal::Singleton < T > \dots \dots$	329
qpp::internal::Singleton < const Codes >	329
qpp::Codes	. 137
qpp::internal::Singleton < const Gates >	329
qpp::Gates	
qpp::internal::Singleton < const Init >	
qpp::Init	
qpp::internal::Singleton < const States >	
qpp::States	. 334
qpp::internal::Singleton< RandomDevices >	329
qpp::RandomDevices	. 326
qpp::NoiseType::StateDependent	
qpp::NoiseType::StateIndependent	
true type	
<pre>app::is_complex< std::complex< T >></pre>	. 207
<pre>app::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval< T</pre>	
>().end()), decltype(*(std::declval< T >().begin()))>>	209
(1.5.1.5.1.1.1.1.1.1.1.1.1.1.1.1.1.1.1.1	00

Chapter 4

Class Index

4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

qpp::Bit_circuit	
Classical reversible circuit simulator	
qpp::Codes	
Const Singleton class that defines quantum error correcting codes	
qpp::exception::CustomException	
Custom exception	
qpp::exception::DimsInvalid	
Invalid dimension(s) exception	
qpp::exception::DimsMismatchCvector	
Dimension(s) mismatch column vector size exception	
qpp::exception::DimsMismatchMatrix	
Dimension(s) mismatch matrix size exception	
qpp::exception::DimsMismatchRvector	
Dimension(s) mismatch row vector size exception	
qpp::exception::DimsMismatchVector	
Dimension(s) mismatch vector size exception	
qpp::exception::DimsNotEqual	
Dimensions not equal exception	
qpp::internal::Display_Impl	
qpp::exception::Duplicates	
System (e.g. std::vector) has duplicates exception	
qpp::Dynamic_bitset	
Dynamic bitset class, allows the specification of the number of bits at runtime	
qpp::internal::EqualEigen	
Functor for comparing Eigen expressions for equality	
qpp::exception::Exception	
Base class for generating Quantum++ custom exceptions	
qpp::Gates	
Const Singleton class that implements most commonly used gates	
qpp::QCircuit::GateStep	
One step consisting only of gates/operators in the circuit	
qpp::internal::HashEigen	
Functor for hashing Eigen expressions	
qpp::IDisplay	
Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) of)

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const 189

8 Class Index

qpp::IJSON	
Abstract class (interface) that mandates the definition of very basic JSON serialization support app::Init	191
Const Singleton class that performs additional initializations/cleanups	192
pp::exception::InvalidIterator	102
···	194
qpp::internal::IOManipEigen	196
qpp::internal::IOManipPointer< PointerType >	199
qpp::internal::IOManipRange< InputIterator >	
qpp::is_complex< T >	
Checks whether the type is a complex type	206
qpp::is_complex< std::complex< T >>	
Checks whether the type is a complex number type, specialization for complex types	207
qpp::is_iterable< T, typename >	
Checks whether T is compatible with an STL-like iterable container \dots	208
qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(std::declt	ecItype(*(std::decIval<
iterable containers	209
qpp::is_matrix_expression< Derived >	
Checks whether the type is an Eigen matrix expression	210
qpp::QCircuit::iterator	
Quantum circuit bound-checking (safe) iterator	211
qpp::make_void< Ts >	
Helper for qpp::to_void<> alias template	216
qpp::exception::MatrixMismatchSubsys	
Matrix mismatch subsystems exception	217
qpp::exception::MatrixNotCvector	
Matrix is not a column vector exception	219
qpp::exception::MatrixNotRvector	
Matrix is not a row vector exception	221
qpp::exception::MatrixNotSquare	
and the state of t	223
qpp::exception::MatrixNotSquareNorCvector	
Matrix is not square nor column vector exception	225
qpp::exception::MatrixNotSquareNorRvector	007
Matrix is not square nor row vector exception	227
qpp::exception::MatrixNotSquareNorVector	000
Matrix is not square nor vector exception	229
qpp::exception::MatrixNotVector	004
Matrix is not a vector exception	231
qpp::QCircuit::MeasureStep One step consisting only of measurements in the circuit	222
pp::exception::NoCodeword	233
Codeword does not exist exception	236
qpp::NoiseBase< T >	200
Base class for all noise models, derive your particular noise model	238
qpp::NoiseType	200
Contains template tags used to specify the noise type	246
qpp::exception::NotBipartite	210
	246
qpp::exception::NotImplemented	2.10
Code not yet implemented	248
qpp::exception::NotQubitCvector	
Column vector is not 2 x 1 exception	250
qpp::exception::NotQubitMatrix	
Matrix is not 2 x 2 exception	252
qpp::exception::NotQubitRvector	
Row vector is not 1 x 2 exception	254

4.1 Class List

qpp::exception::NotQubitSubsys	
Subsystems are not qubits exception	256
qpp::exception::NotQubitVector	
'	258
qpp::exception::OutOfRange	
	260
qpp::exception::PermInvalid	000
Invalid permutation exception	262
qpp::exception::PermMismatchDims	264
Permutation mismatch dimensions exception	204
Quantum circuit class	267
qpp::QEngine	
Quantum circuit engine, executes qpp::QCircuit	297
qpp::QNoisyEngine < NoiseModel >	
Noisy quantum circuit engine, executes qpp::QCircuit	308
qpp::QubitAmplitudeDampingNoise	
	312
qpp::QubitBitFlipNoise	
Qubit bit flip noise	314
qpp::QubitBitPhaseFlipNoise	015
Qubit bit-phase flip (dephasing) noise	315
qpp::QubitDepolarizingNoise Qubit depolarizing noise	317
qpp::QubitPhaseDampingNoise	317
Qubit phase damping noise, as described in Nielsen and Chuang	318
qpp::QubitPhaseFlipNoise	0.0
	320
qpp::exception::QuditAlreadyMeasured	
	321
qpp::QuditDepolarizingNoise	
Qudit depolarizing noise	323
qpp::RandomDevices	
, ,	326
qpp::internal::Singleton< T >	
Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously	
recurring template pattern)	329
qpp::exception::SizeMismatch	000
Size mismatch exception	332
<pre>qpp::NoiseType::StateDependent</pre>	334
qpp::NoiseType::StateIndependent	334
Template tag, used whenever the noise is state-independent	334
qpp::States	00 1
Const Singleton class that implements most commonly used states	334
qpp::exception::SubsysMismatchDims	
Subsystems mismatch dimensions exception	344
qpp::Timer< T, CLOCK T>	
Chronometer	346
qpp::exception::TypeMismatch	
71	350
qpp::exception::UndefinedType	
71 1	352
qpp::exception::Unknown	
Unknown exception	354
qpp::QCircuit::iterator::value_type_	050
Value type class for qpp::QCircuit::iterator	356

10		Class Index

qpp::exception::ZeroSize													
Object has zero size exception							 						360

Chapter 5

File Index

5.1 File List

Here is a list of all files with brief descriptions:

constants.h	
Constants	374
entanglement.h	
Entanglement functions	375
entropies.h	
Entropy functions	377
functions.h	
Generic quantum computing functions	378
input_output.h	
Input/output functions	383
instruments.h	
Measurement functions	384
number_theory.h	
Number theory functions	390
operations.h	
Quantum operation functions	392
qpp.h	
Quantum++ main header file, includes all other necessary headers	394
random.h	
Randomness-related functions	396
statistics.h	
Statistics functions	397
traits.h	001
Type traits	398
types.h	400
Type aliases	400
classes/codes.h	001
Quantum error correcting codes	365
classes/exception.h	001
Exceptions	365
classes/gates.h	00-
9	367
classes/idisplay.h	
Display interface via the non-virtual interface (NVI) and very basic JSON serialization support	001
interface	368

12 File Index

classes/init.h	
Initialization	369
classes/noise.h	
Noise models	370
classes/random_devices.h	
Random devices	371
classes/reversible.h	
Support for classical reversible circuits	371
classes/states.h	
Quantum states	372
classes/timer.h	
Timing	373
classes/circuits/circuits.h	
Qudit quantum circuits	363
classes/circuits/engines.h	
Qudit quantum engines	364
experimental/experimental.h	
Experimental/test functions/classes	378
internal/util.h	
Internal utility functions	387
internal/classes/iomanip.h	
Input/output manipulators	386
internal/classes/singleton.h	
Singleton pattern via CRTP	387
MATLAB/matlab.h	
Input/output interfacing with MATLAR	389

Chapter 6

Namespace Documentation

6.1 qpp Namespace Reference

Quantum++ main namespace.

Namespaces

· exception

Quantum++ exception hierarchy namespace.

· experimental

Experimental/test functions/classes, do not use or modify.

internal

Internal utility functions, do not use them directly or modify them.

literals

Classes

• class Bit_circuit

Classical reversible circuit simulator.

• class Codes

const Singleton class that defines quantum error correcting codes

· class Dynamic_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime.

· class Gates

const Singleton class that implements most commonly used gates

class IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

class IJSON

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

class Init

const Singleton class that performs additional initializations/cleanups

· struct is complex

Checks whether the type is a complex type.

• struct is_complex< std::complex< T > >

Checks whether the type is a complex number type, specialization for complex types.

· struct is_iterable

Checks whether T is compatible with an STL-like iterable container.

 $\bullet \ \ struct\ is_iterable < T,\ to_void < \ decltype(std::declval < T>().begin()),\ decltype(std::declval < T>().end()),\ decltype(*(std::declval < T>().end())),\ decltype(*(std::declval < T>().end()$

Checks whether T is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

• struct is_matrix_expression

Checks whether the type is an Eigen matrix expression.

· struct make void

Helper for qpp::to_void<> alias template.

· class NoiseBase

Base class for all noise models, derive your particular noise model.

class NoiseType

Contains template tags used to specify the noise type.

class QCircuit

Quantum circuit class.

class QEngine

Quantum circuit engine, executes qpp::QCircuit.

class QNoisyEngine

Noisy quantum circuit engine, executes qpp::QCircuit.

· class QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

• class QubitBitFlipNoise

Qubit bit flip noise.

· class QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

· class QubitDepolarizingNoise

Qubit depolarizing noise.

• class QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

· class QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

· class QuditDepolarizingNoise

Qudit depolarizing noise.

· class RandomDevices

Singleton class that manages the source of randomness in the library.

· class States

const Singleton class that implements most commonly used states

class Timer

Chronometer.

Typedefs

```
    template<typename... Ts>
        using to_void = typename make_void< Ts... >::type
```

Alias template that implements the proposal for void_t.

using idx = std::size_t

Non-negative integer index, make sure you use an unsigned type.

• using bigint = long long int

Big integer.

• using cplx = std::complex< double >

Complex number in double precision.

• using ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector.

• using bra = Eigen::RowVectorXcd

Complex (double precision) dynamic Eigen row vector.

using cmat = Eigen::MatrixXcd

Complex (double precision) dynamic Eigen matrix.

using dmat = Eigen::MatrixXd

Real (double precision) dynamic Eigen matrix.

• template<typename Scalar >

```
using dyn_mat = Eigen::Matrix < Scalar, Eigen::Dynamic, Eigen::Dynamic >
```

Dynamic Eigen matrix over the field specified by Scalar.

• template<typename Scalar >

```
using dyn_col_vect = Eigen::Matrix < Scalar, Eigen::Dynamic, 1 >
```

Dynamic Eigen column vector over the field specified by Scalar.

template<typename Scalar >

```
using dyn_row_vect = Eigen::Matrix < Scalar, 1, Eigen::Dynamic >
```

Dynamic Eigen row vector over the field specified by Scalar.

Enumerations

• enum { RES, PROB, ST }

Constants to be used by std::get<> on the result of qpp::measure(), qpp_measure_seq() etc.

Functions

cplx omega (idx D)

D-th root of unity.

 $\bullet \ \ \text{template}{<} \text{typename Derived} >$

dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx >
&dims)

Schmidt coefficients of the bi-partite pure state A.

• template<typename Derived >

```
dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2)
```

Schmidt coefficients of the bi-partite pure state A.

template<typename Derived >

```
cmat schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
```

Schmidt basis on Alice side.

template<typename Derived >

```
cmat schmidtA (const Eigen::MatrixBase< Derived > &A, idx d=2)
```

Schmidt basis on Alice side.

template<typename Derived >

```
cmat schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
```

Schmidt basis on Bob side.

template<typename Derived >

```
cmat schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2)
```

Schmidt basis on Bob side.

• template<typename Derived >

std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)

Schmidt probabilities of the bi-partite pure state A.

```
• template<typename Derived >
  std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt probabilities of the bi-partite pure state A.
template<typename Derived >
  double entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Entanglement of the bi-partite pure state A.
template<typename Derived >
  double entanglement (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Entanglement of the bi-partite pure state A.
• template<typename Derived >
  double gconcurrence (const Eigen::MatrixBase< Derived > &A)
      G-concurrence of the bi-partite pure state A.

    template < typename Derived >

  double negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double negativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Logarithmic negativity of the bi-partite mixed state A.
• template<typename Derived >
  double lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double concurrence (const Eigen::MatrixBase< Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.

    template<typename Derived >

  double entropy (const Eigen::MatrixBase< Derived > &A)
      von-Neumann entropy of the density matrix A

    double entropy (const std::vector< double > &prob)

      Shannon entropy of the probability distribution prob.

    template<typename Derived >

  double renyi (const Eigen::MatrixBase< Derived > &A, double alpha)
      Renyi- \alpha entropy of the density matrix A, for \alpha \geq 0.

    double renyi (const std::vector< double > &prob, double alpha)

      Renyi- \alpha entropy of the probability distribution prob, for \alpha > 0.
• template<typename Derived >
  double tsallis (const Eigen::MatrixBase< Derived > &A, double q)
      Tsallis- q entropy of the density matrix A, for q \geq 0.

    double tsallis (const std::vector< double > &prob, double q)

      Tsallis- q entropy of the probability distribution prob, for q \geq 0.
• template<typename Derived >
  double qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx > &subsysB, const std::vector< idx > &dims)
      Quantum mutual information between 2 subsystems of a composite system.

    template<typename Derived >

  \label{eq:const_decomposition} \mbox{double } \mbox{qmutualinfo} \mbox{ (const Eigen::MatrixBase} < \mbox{Derived} > \&\mbox{A, const std::vector} < \mbox{idx} > \&\mbox{subsysA, const}
  std::vector< idx > &subsysB, idx d=2)
      Quantum mutual information between 2 subsystems of a composite system.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > transpose (const Eigen::MatrixBase< Derived > &A)
      Transpose.
```

```
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > conjugate (const Eigen::MatrixBase< Derived > &A)
     Complex conjugate.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > adjoint (const Eigen::MatrixBase< Derived > &A)
     Adjoint.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > inverse (const Eigen::MatrixBase< Derived > &A)
     Inverse.

    template<typename Derived >

  Derived::Scalar trace (const Eigen::MatrixBase< Derived > &A)
     Trace.

    template<typename Derived >

  Derived::Scalar det (const Eigen::MatrixBase< Derived > &A)
     Determinant.
• template<typename Derived >
  Derived::Scalar logdet (const Eigen::MatrixBase< Derived > &A)
     Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar sum (const Eigen::MatrixBase< Derived > &A)
     Element-wise sum of A.

    template<typename Derived >

  Derived::Scalar prod (const Eigen::MatrixBase< Derived > &A)
     Element-wise product of A.

    template<typename Derived >

  double norm (const Eigen::MatrixBase< Derived > &A)
     Frobenius norm.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > normalize (const Eigen::MatrixBase< Derived > &A)
     Normalizes state vector (column or row vector) or density matrix.

    template<typename Derived >

  std::pair< dyn_col_vect< cplx >, cmat > eig (const Eigen::MatrixBase< Derived > &A)
     Full eigen decomposition.

    template<typename Derived >

  dyn_col_vect< cplx > evals (const Eigen::MatrixBase< Derived > &A)
     Eigenvalues.

    template<typename Derived >

  cmat evects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors.

    template<typename Derived >

  std::pair< dyn col vect< double >, cmat > heig (const Eigen::MatrixBase< Derived > &A)
     Full eigen decomposition of Hermitian expression.
• template<typename Derived >
  dyn_col_vect< double > hevals (const Eigen::MatrixBase< Derived > &A)
     Hermitian eigenvalues.

    template<typename Derived >

  cmat hevects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors of Hermitian matrix.
• template<typename Derived >
  std::tuple < cmat, dyn col vect < double >, cmat > svd (const Eigen::MatrixBase < Derived > &A)
     Full singular value decomposition.

    template<typename Derived >

  dyn_col_vect< double > svals (const Eigen::MatrixBase< Derived > &A)
```

Kronecker product.

```
Singular values.
• template<typename Derived >
  cmat svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.
• template<typename Derived >
  cmat svdV (const Eigen::MatrixBase< Derived > &A)
     Right singular vectors.
• template<typename Derived >
  cmat funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)
template<typename Derived >
  cmat sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.

    template<typename Derived >

  cmat absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.
• template<typename Derived >
  cmat expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.

    template<typename Derived >

  cmat logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.

    template<typename Derived >

  cmat sinm (const Eigen::MatrixBase< Derived > &A)
• template<typename Derived >
  cmat cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.

    template<typename Derived >

  cmat spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > powm (const Eigen::MatrixBase< Derived > &A, idx n)
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.
• template<typename Derived >
  double schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const type-
  name Derived::Scalar &))
     Functor.
template<typename T >
  dyn_mat< typename T::Scalar > kron (const T &head)
     Kronecker product.

    template<typename T, typename... Args>

  dyn_mat< typename T::Scalar > kron (const T &head, const Args &... tail)
     Kronecker product.
template<typename Derived >
  dyn_mat< typename Derived::Scalar > kron (const std::vector< Derived > &As)
     Kronecker product.
template<typename Derived >
  dyn mat< typename Derived::Scalar > kron (const std::initializer list< Derived > &As)
```

```
    template<typename Derived >

  dyn_mat< typename Derived::Scalar > kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Kronecker power.
template<typename T >
  dyn mat< typename T::Scalar > dirsum (const T &head)
     Direct sum.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > dirsum (const T &head, const Args &... tail)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > dirsum (const std::vector< Derived > &As)
     Direct sum.
• template<typename Derived >
  dyn mat< typename Derived::Scalar > dirsum (const std::initializer list< Derived > &As)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > reshape (const Eigen::MatrixBase< Derived > &A, idx rows, idx
  cols)
     Reshape.

    template<typename Derived1 , typename Derived2 >

  dyn mat< typename Derived1::Scalar > comm (const Eigen::MatrixBase< Derived1 > &A, const Eigen::↔
  MatrixBase< Derived2 > &B)
     Commutator.
- template<typename Derived1 , typename Derived2 >
  dyn_mat< typename Derived1::Scalar > anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > prj (const Eigen::MatrixBase< Derived > &A)
     Projector.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > grams (const std::vector< Derived > &As)
     Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > grams (const std::initializer_list< Derived > &As)
     Gram-Schmidt orthogonalization.

    template < typename Derived >

  dyn_mat< typename Derived::Scalar > grams (const Eigen::MatrixBase< Derived > &A)
     Gram-Schmidt orthogonalization.

    std::vector < idx > n2multiidx (idx n, const std::vector < idx > &dims)

     Non-negative integer index to multi-index.

    idx multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

     Multi-index to non-negative integer index.

    ket mket (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Multi-partite qudit ket.

    ket mket (const std::vector < idx > &mask, idx d=2)

     Multi-partite qudit ket.

    cmat mprj (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Projector onto multi-partite qudit ket.

    cmat mprj (const std::vector< idx > &mask, idx d=2)
```

Projector onto multi-partite qudit ket.

• template<typename InputIterator >

```
std::vector< double > abssq (InputIterator first, InputIterator last)
```

Computes the absolute values squared of an STL-like range of complex numbers.

template<typename Container >

```
std::vector< double > abssq (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)
```

Computes the absolute values squared of an STL-like container.

• template<typename Derived >

```
std::vector< double > abssq (const Eigen::MatrixBase< Derived > &A)
```

Computes the absolute values squared of an Eigen expression.

• template<typename InputIterator >

```
std::iterator_traits< InputIterator >::value_type sum (InputIterator first, InputIterator last)
```

Element-wise sum of an STL-like range.

template<typename Container >

```
Container::value_type sum (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)
```

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

```
std::iterator traits < InputIterator >::value type prod (InputIterator first, InputIterator last)
```

Element-wise product of an STL-like range.

template<typename Container >

Container::value_type prod (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Element-wise product of the elements of an STL-like container.

template<typename Derived >

```
dyn col vect< typename Derived::Scalar > rho2pure (const Eigen::MatrixBase< Derived > &A)
```

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

std::vector< idx > complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

• template<typename Derived >

```
std::vector< double > rho2bloch (const Eigen::MatrixBase< Derived > &A)
```

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

• template<typename Derived >

```
std::size_t hash_eigen (const Eigen::MatrixBase< Derived > &A, std::size_t seed=0)
```

Computes the hash of en Eigen matrix/vector/expression.

• template<typename Derived >

```
internal::IOManipEigen disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
```

Eigen expression ostream manipulator.

internal::IOManipEigen disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

 $\bullet \ \ \text{template}{<} \text{typename InputIterator} >$

internal::IOManipRange< InputIterator > disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)

Range ostream manipulator.

• template<typename Container >

internal::IOManipRange< typename Container::const_iterator > disp (const Container &c, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop, typename std ::enable_if< is_iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

template<typename PointerType >
 internal::IOManipPointer< PointerType > disp (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)

C-style pointer ostream manipulator.

• template<typename Derived >

void save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.

• template<typename Derived >

dyn_col_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)

Generalized inner product.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple < idx, std::vector < cmat >> measure (const Eigen::MatrixBase < Derived > &A, const std::vector < cmat > &Ks, const std::vector < idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

template<typename Derived >

std::tuple < idx, std::vector < double >, std::vector < cmat > > measure (const Eigen::MatrixBase < Derived > &A, const cmat &V, const std::vector < idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template<typename Derived >

std::tuple< std::vector< idx >, double, cmat > measure_seq (const Eigen::MatrixBase< Derived > &A, std::vector< idx > target, idx d=2)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template < typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< cplx > >::type loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::

Scalar > >::type loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

std::vector< int > x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

• bigint gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > invperm (const std::vector< idx > &perm)

Inverse permutation.

• std::vector< idx > compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

std::vector< bigint > factors (bigint a)

Prime factor decomposition.

• bigint modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

bigint modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple < bigint, bigint > egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

• bigint modiny (bigint a, bigint p)

Modular inverse of a mod p.

bool isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

bigint randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

- std::vector < std::pair < int, int > > convergents (const std::vector < int > &cf)

Convergents.

std::vector< std::pair< int, int > > convergents (double x, idx N)

Convergents.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, const
std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, idx
d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)
```

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, const std::vector< idx > &dims)
```

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, idx d=2)
```

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat kraus2super (const std::vector< cmat > &Ks)

Superoperator matrix.

cmat kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector < cmat > choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

 $\bullet \ \ \mathsf{template}{<}\mathsf{typename} \ \mathsf{Derived}>$

```
dyn_mat< typename Derived::Scalar > ptrace1 (const Eigen::MatrixBase< Derived > &A, const std← ::vector< idx > &dims)
```

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector < idx > &dims)

Partial trace.

template<typename Derived >

dyn mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector<
idx > &target, const std::vector< idx > &dims)

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector
idx > &target, idx d=2)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptranspose (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, const std::vector< idx > &dims)

Partial transpose.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > ptranspose (const Eigen::MatrixBase< Derived > &A, const std ← ::vector < idx > &target, idx d=2)

Partial transpose.

• template<typename Derived >

Subsystem permutation.

template<typename Derived >

dyn_mat< typename Derived::Scalar > syspermute (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &perm, idx d=2)

Subsystem permutation.

• template<typename Derived >

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool
swap=true)

Qudit quantum Fourier transform.

double rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

• bigint rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx randidx (idx a=std::numeric_limits< idx >::min(), idx b=std::numeric_limits< idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

template<typename Derived >

Derived rand (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double a QPP_UNUSED_=0, double b QPP_UNUSED =1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

• template<>

```
dmat rand (idx rows, idx cols, double a, double b)
```

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

template<>

```
cmat rand (idx rows, idx cols, double a, double b)
```

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

• template<typename Derived >

Derived randn (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double mean QPP_UNUSED_=0, double sigma QPP_UNUSED_=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

```
dmat randn (idx rows, idx cols, double mean, double sigma)
```

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

template<>

```
cmat randn (idx rows, idx cols, double mean, double sigma)
```

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

• double randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

• cmat randU (idx D=2)

Generates a random unitary matrix.

· cmat randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat randH (idx D=2)

Generates a random Hermitian matrix.

ket randket (idx D=2)

Generates a random normalized ket (pure state vector)

cmat randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.

std::vector< double > uniform (idx N)

Uniform probability distribution vector.

std::vector< double > marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > marginalY (const dmat &probXY)

Marginal distribution.

template<typename Container >
 double avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable<
 Container >::value >::type *=nullptr)

Average.

• template<typename Container >

double cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Covariance.

• template<typename Container >

double var (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Variance.

• template<typename Container >

double sigma (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Standard deviation.

• template<typename Container >

double cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Correlation.

Variables

constexpr double chop = 1e-16

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

• constexpr idx maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

constexpr double pi = 3.141592653589793238462643383279502884

 π

• constexpr double ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

constexpr double infty = std::numeric_limits<double>::max()

Used to denote infinity in double precision.

6.1.1 Detailed Description

Quantum++ main namespace.

6.1.2 Typedef Documentation

6.1.2.1 bigint

```
using qpp::bigint = typedef long long int
```

Big integer.

```
6.1.2.2 bra
```

```
using qpp::bra = typedef Eigen::RowVectorXcd
```

Complex (double precision) dynamic Eigen row vector.

6.1.2.3 cmat

```
using qpp::cmat = typedef Eigen::MatrixXcd
```

Complex (double precision) dynamic Eigen matrix.

6.1.2.4 cplx

```
using qpp::cplx = typedef std::complex<double>
```

Complex number in double precision.

6.1.2.5 dmat

```
using qpp::dmat = typedef Eigen::MatrixXd
```

Real (double precision) dynamic Eigen matrix.

6.1.2.6 dyn_col_vect

```
template<typename Scalar >
using qpp::dyn_col_vect = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, 1>
```

Dynamic Eigen column vector over the field specified by Scalar.

Example:

```
// type of colvect is Eigen::Matrix<float, Eigen::Dynamic, 1>
dyn_col_vect<float> colvect(2);
```

```
6.1.2.7 dyn_mat
```

```
template<typename Scalar >
using qpp::dyn_mat = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, Eigen::Dynamic>
```

Dynamic Eigen matrix over the field specified by Scalar.

Example:

```
// type of mat is Eigen::Matrix<float, Eigen::Dynamic, Eigen::Dynamic>
dyn_mat<float> mat(2, 3);
```

6.1.2.8 dyn_row_vect

```
template<typename Scalar >
using qpp::dyn_row_vect = typedef Eigen::Matrix<Scalar, 1, Eigen::Dynamic>
```

Dynamic Eigen row vector over the field specified by Scalar.

Example:

```
// type of rowvect is Eigen::Matrix<float, 1, Eigen::Dynamic>
dyn_row_vect<float> rowvect(3);
```

6.1.2.9 idx

```
using qpp::idx = typedef std::size_t
```

Non-negative integer index, make sure you use an unsigned type.

6.1.2.10 ket

```
using qpp::ket = typedef Eigen::VectorXcd
```

Complex (double precision) dynamic Eigen column vector.

6.1.2.11 to_void

```
template<typename... Ts>
using qpp::to_void = typedef typename make_void<Ts...>::type
```

Alias template that implements the proposal for void_t.

See also

```
http://www.open-std.org/jtc1/sc22/wg21/docs/papers/2014/n3911
```

6.1.3 Enumeration Type Documentation

6.1.3.1 anonymous enum

```
anonymous enum
```

Constants to be used by std::get<> on the result of qpp::measure(), qpp_measure_seq() etc.

Enumerator

RES	Measurement result(s)
PROB	Probabilit(y)/(ies)
ST	Output state(s)

6.1.4 Function Documentation

6.1.4.1 absm()

Matrix absolute value.

Parameters

```
A Eigen expression
```

Returns

Matrix absolute value of A

6.1.4.2 abssq() [1/3]

Computes the absolute values squared of an STL-like range of complex numbers.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Real vector consisting of the range absolute values squared

Computes the absolute values squared of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Real vector consisting of the container's absolute values squared

Computes the absolute values squared of an Eigen expression.

Parameters

```
A Eigen expression
```

Returns

Real vector consisting of the absolute values squared

6.1.4.5 adjoint()

Adjoint.

```
A Eigen expression
```

Adjoint (Hermitian conjugate) of A, as a dynamic matrix over the same scalar field as A

6.1.4.6 anticomm()

Anti-commutator.

See also

qpp::comm()

Anti-commutator $\{A,B\}=AB+BA$. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
В	Eigen expression

Returns

Anti-commutator AB + BA, as a dynamic matrix over the same scalar field as A

6.1.4.7 apply() [1/5]

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

state	Eigen expression	
Α	Eigen expression	
Gataligaeti :	catarget by Substant indexes where the gate A is applied	
dims	Dimensions of the multi-partite system	

Gate A applied to the part target of state

```
6.1.4.8 apply() [2/5]
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

Returns

Gate A applied to the part target of state

```
6.1.4.9 apply() [3/5]
```

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

Α	Eigen expression
Ks	Set of Kraus operators

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes where the Kraus operators Ks are applied
dims	Dimensions of the multi-partite system

Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*.

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes where the Kraus operators Ks are applied
d	Subsystem dimensions

Output density matrix after the action of the channel

6.1.4.12 applyCTRL() [1/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate A must match the dimension of *target*. Also, all control subsystems in *ctrl* must have the same dimension.

Parameters

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

Returns

CTRL-A gate applied to the part target of state

6.1.4.13 applyCTRL() [2/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

Returns

CTRL-A gate applied to the part target of state

6.1.4.14 applyQFT()

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

Parameters

Α	Eigen expression	
target	Subsystem indexes where the QFT is applied	
d	Subsystem dimensions	
swap	Swaps the qubits/qudits at the end (true by default)	

Returns

Qudit Quantum Fourier transform applied to the part target of A

6.1.4.15 applyTFQ()

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::applyTFQ (
```

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & target,
idx d = 2,
bool swap = true )
```

Applies the inverse (adjoint) qudit quantum Fourier transform to the part *target* of the multi-partite state vector or density matrix *A*.

Parameters

Α	Eigen expression	
target	Subsystem indexes where the TFQ is applied	
d	Subsystem dimensions	
swap	Swaps the qubits/qudits at the end (true by default)	

Returns

Inverse (adjoint) qudit Quantum Fourier transform applied to the part target of A

6.1.4.16 avg()

Average.

Parameters

prob	Real probability vector representing the probability distribution of X
X	Real random variable values represented by an STL-like container

Returns

Average of X

6.1.4.17 bloch2rho()

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

See also

qpp::rho2bloch()

r 3-dimensional real vector

Returns

Qubit density matrix

6.1.4.18 choi2kraus()

Orthogonal Kraus operators from Choi matrix.

See also

qpp::kraus2choi()

Extracts a set of orthogonal (under Hilbert-Schmidt operator norm) Kraus operators from the Choi matrix A

Note

The Kraus operators satisfy $Tr(K_i^\dagger K_j) = \delta_{ij}$ for all $i \neq j$

Parameters

A Choi matrix

Returns

Set of orthogonal Kraus operators

6.1.4.19 choi2super()

Converts Choi matrix to superoperator matrix.

See also

qpp::super2choi()

```
A Choi matrix
```

Returns

Superoperator matrix

6.1.4.20 comm()

Commutator.

See also

qpp::anticomm()

Commutator [A, B] = AB - BA. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
В	Eigen expression

Returns

Commutator AB-BA, as a dynamic matrix over the same scalar field as ${\it A}$

6.1.4.21 complement()

```
std::vector<idx> qpp::complement (
    std::vector< idx > subsys,
    idx n ) [inline]
```

Constructs the complement of a subsystem vector.

Parameters

subsys	Subsystem vector
n	Total number of systems

Returns

Complement of *subsys* with respect to the set $\{0, 1, \dots, n-1\}$

6.1.4.22 compperm()

Compose permutations.

Parameters

perm	Permutation
sigma	Permutation

Returns

Composition of the permutations $perm \circ sigma = perm(sigma)$

6.1.4.23 concurrence()

Wootters concurrence of the bi-partite qubit mixed state A.

Parameters

```
A Eigen expression
```

Returns

Wootters concurrence

6.1.4.24 conjugate()

Complex conjugate.

```
A Eigen expression
```

Returns

Complex conjugate of A, as a dynamic matrix over the same scalar field as A

6.1.4.25 contfrac2x()

```
double qpp::contfrac2x ( const std::vector< int > & cf, idx N = idx(-1) ) [inline]
```

Real representation of a simple continued fraction.

See also

```
qpp::x2contfrac()
```

Note

If N is greater than the size of cf (by default it is), then all terms in cf are considered.

Parameters

cf	Integer vector containing the simple continued fraction expansion
Ν	Number of terms considered in the continued fraction expansion.

Returns

Real representation of the simple continued fraction

6.1.4.26 convergents() [1/2]

```
std::vector<std::pair<int, int> > qpp::convergents ( const std::vector< int > & cf ) [inline]
```

Convergents.

See also

qpp::contfrac2x() and qpp::x2contfrac()

```
cf Continued fraction
```

Returns

Vector of convergents pairs (a_k, b_k) that approximate the number represented by the continued fraction

6.1.4.27 convergents() [2/2]

```
std::vector<std::pair<int, int> > qpp::convergents ( double x, idx N) [inline]
```

Convergents.

See also

```
qpp::contfrac2x() and qpp::x2contfrac()
```

Note

In the continued fraction expansion of x has less terms than N, then the series of convergents is truncated to the number of terms in the continued fraction expansion of x.

Parameters

Χ	Real number
Ν	Number of convergents.

Returns

Vector of convergents pairs (a_k, b_k) that approximate the number x

6.1.4.28 cor()

Correlation.

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels the rows, Y labels the columns)
X	Real random variable values represented by an STL-like container
Y	Real random variable values represented by an STL-like container

Returns

Correlation of X and Y

6.1.4.29 cosm()

Matrix cos.

Parameters

```
A Eigen expression
```

Returns

Matrix cosine of A

6.1.4.30 cov()

Covariance.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels the rows, Y labels the columns)
X	Real random variable values represented by an STL-like container
Y	Real random variable values represented by an STL-like container

Returns

Covariance of X and Y

6.1.4.31 cwise()

Functor.

Parameters

Α	Eigen expression
f	Pointer-to-function from scalars of A to OutputScalar

Returns

Component-wise f(A), as a dynamic matrix over the *OutputScalar* scalar field

6.1.4.32 det()

Determinant.

Parameters

```
A Eigen expression
```

Returns

Determinant of A, as a scalar over the same scalar field as A. Returns $\pm \infty$ when the determinant overflows/underflows.

Direct sum.

See also

qpp::dirsumpow()

Used to stop the recursion for the variadic template version of qpp::dirsum()

Parameters

```
head Eigen expression
```

Returns

Its argument head

6.1.4.34 dirsum() [2/4]

Direct sum.

See also

qpp::dirsumpow()

Parameters

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

Returns

Direct sum of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.4.35 dirsum() [3/4]

Direct sum.

See also

qpp::dirsumpow()

As std::vector of Eigen expressions

Returns

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

See also

qpp::dirsumpow()

Parameters

As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}

Returns

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.4.37 dirsumpow()

Direct sum power.

See also

qpp::dirsum()

Α	Eigen expression
n	Non-negative integer

Returns

Direct sum of A with itself n times $A^{\oplus n}$, as a dynamic matrix over the same scalar field as A

Eigen expression ostream manipulator.

Parameters

Α	Eigen expression
chop	Set to zero the elements smaller in absolute value than <i>chop</i>

Returns

Instance of qpp::internal::IOManipEigen

Complex number ostream manipulator.

Parameters

Z	Complex number (or any other type implicitly cast-able to std::complex <double>)</double>
chop	Set to zero the elements smaller in absolute value than <i>chop</i>

Returns

Instance of qpp::internal::IOManipEigen

```
6.1.4.40 disp() [3/5]
```

Range ostream manipulator.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipRange

```
6.1.4.41 disp() [4/5]
```

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

Parameters

С	Container
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipRange

6.1.4.42 disp() [5/5]

C-style pointer ostream manipulator.

Parameters

p	Pointer to the first element
N	Number of elements to be displayed
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipPointer

6.1.4.43 egcd()

Extended greatest common divisor of two integers.

See also

```
qpp::gcd()
```

Parameters

а	Integer
b	Integer

Returns

Tuple of: 1. Integer m, 2. Integer n, and 3. Non-negative integer gcd(a,b) such that ma + nb = gcd(a,b)

6.1.4.44 eig()

Full eigen decomposition.

See also

qpp::heig()

Parameters

```
A Eigen expression
```

Returns

Pair of: 1. Eigenvalues of A, as a complex dynamic column vector, and 2. Eigenvectors of A, as columns of a complex dynamic matrix

6.1.4.45 entanglement() [1/2]

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

```
qpp::entropy()
```

Parameters

Α	Eigen expression	
dims	Dimensions of the bi-partite system	

Returns

Entanglement, with the logarithm in base 2

6.1.4.46 entanglement() [2/2]

```
template<typename Derived > double qpp::entanglement ( const Eigen::MatrixBase< Derived > & A, idx d = 2)
```

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

```
qpp::entropy()
```

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Entanglement, with the logarithm in base 2

6.1.4.47 entropy() [1/2] template<typename Derived > double qpp::entropy (

const Eigen::MatrixBase< Derived > & A)

von-Neumann entropy of the density matrix A

Parameters

```
A Eigen expression
```

Returns

von-Neumann entropy, with the logarithm in base 2

Shannon entropy of the probability distribution prob.

prob Real probability vector

Returns

Shannon entropy, with the logarithm in base 2

6.1.4.49 evals()

Eigenvalues.

See also

qpp::hevals()

Parameters

A Eigen expression

Returns

Eigenvalues of A, as a complex dynamic column vector

6.1.4.50 evects()

Eigenvectors.

See also

qpp::hevects()

Parameters

A Eigen expression

Returns

Eigenvectors of A, as columns of a complex dynamic matrix

6.1.4.51 expm()

Matrix exponential.

Parameters

```
A Eigen expression
```

Returns

Matrix exponential of A

6.1.4.52 factors()

Prime factor decomposition.

Note

Runs in $\mathcal{O}(\sqrt{n})$ time complexity

Parameters

```
a Integer different from 0, 1 or -1
```

Returns

Integer vector containing the factors

6.1.4.53 funm()

```
template<typename Derived >
cmat qpp::funm (
```

```
const Eigen::MatrixBase< Derived > & A,
cplx(*)(const cplx &) f )
```

Functional calculus f(A)

Parameters

Α	A Eigen expression	
f	Pointer-to-function from complex to complex	

Returns

f(A)

Greatest common divisor of two integers.

See also

qpp::lcm()

Parameters

а	Integer
b	Integer

Returns

Greatest common divisor of a and b

Greatest common divisor of a list of integers.

See also

qpp::lcm()

```
as List of integers
```

Returns

Greatest common divisor of all numbers in as

6.1.4.56 gconcurrence()

G-concurrence of the bi-partite pure state A.

Note

Both local dimensions must be equal

Uses qpp::logdet() to avoid overflows

See also

qpp::logdet()

Parameters

```
A Eigen expression
```

Returns

G-concurrence

6.1.4.57 grams() [1/3]

Gram-Schmidt orthogonalization.

As std::vector of Eigen expressions as column vectors

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

Gram-Schmidt orthogonalization.

Parameters

As std::initializer_list of Eigen expressions as column vectors

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

Gram-Schmidt orthogonalization.

Parameters

A Eigen expression, the input vectors are the columns of A

Returns

Gram-Schmidt vectors of the columns of A, as columns of a dynamic matrix over the same scalar field as A

6.1.4.60 hash_eigen()

Computes the hash of en Eigen matrix/vector/expression.

Note

Code taken from boost::hash_combine(), see https://www.boost.org/doc/libs/1_69_← 0/doc/html/hash/reference.html#boost.hash_combine

Parameters

Α	Eigen expression
seed	Seed, 0 by default

Returns

Hash of its argument

6.1.4.61 heig()

Full eigen decomposition of Hermitian expression.

See also

qpp::eig()

Parameters

A Eigen expression

Returns

Pair of: 1. Eigenvalues of A, as a real dynamic column vector, and 2. Eigenvectors of A, as columns of a complex dynamic matrix

6.1.4.62 hevals()

Hermitian eigenvalues.

See also

qpp::evals()

Parameters

```
A Eigen expression
```

Returns

Eigenvalues of Hermitian A, as a real dynamic column vector

6.1.4.63 hevects()

Eigenvectors of Hermitian matrix.

See also

qpp::evects()

Parameters

```
A Eigen expression
```

Returns

Eigenvectors of Hermitian matrix A, as columns of a complex matrix

6.1.4.64 inverse()

Inverse.

```
A Eigen expression
```

Returns

Inverse of A, as a dynamic matrix over the same scalar field as A

6.1.4.65 invperm()

Inverse permutation.

Parameters

perm	Permutation
------	-------------

Returns

Inverse of the permutation perm

6.1.4.66 ip() [1/2]

Generalized inner product.

Parameters

phi	Column vector Eigen expression	
psi	Column vector Eigen expression	
subsys	Subsystem indexes over which phi is defined	
dims	Dimensions of the multi-partite system	

Returns

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

Generalized inner product.

Parameters

phi	Column vector Eigen expression
psi	Column vector Eigen expression
subsys	Subsystem indexes over which phi is defined
d	Subsystem dimensions

Returns

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

6.1.4.68 isprime()

```
bool qpp::isprime ( bigint p, idx k = 80 ) [inline]
```

Primality test based on the Miller-Rabin's algorithm.

Parameters

р	Integer different from 0, 1 or -1
k	Number of iterations. The probability of a false positive is 2^{-k} .

Returns

True if the number is (most-likely) prime, false otherwise

6.1.4.69 kraus2choi()

Choi matrix.

See also

qpp::choi2kraus()

Constructs the Choi matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|$, $|0\rangle\langle 1|$ etc.

Note

The superoperator matrix S and the Choi matrix C are related by $S_{ab,mn}=C_{ma,nb}$

Parameters

```
Ks Set of Kraus operators
```

Returns

Choi matrix

6.1.4.70 kraus2super()

Superoperator matrix.

Constructs the superoperator matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|$, $|0\rangle\langle 1|$ etc.

Parameters

```
Ks Set of Kraus operators
```

Returns

Superoperator matrix

Kronecker product.

•		
See	а	เรด

qpp::kronpow()

Used to stop the recursion for the variadic template version of app::kron()

head Eigen expressio	n
------------------------	---

Returns

Its argument head

Kronecker product.

See also

qpp::kronpow()

Parameters

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

Returns

Kronecker product of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Kronecker product.

See also

qpp::kronpow()

```
As std::vector of Eigen expressions
```

Returns

Kronecker product of all elements in *As*, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

See also

qpp::kronpow()

Parameters

```
As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}
```

Returns

Kronecker product of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.4.75 kronpow()

Kronecker power.

See also

qpp::kron()

Α	Eigen expression
n	Non-negative integer

Returns

Kronecker product of A with itself n times $A^{\otimes n}$, as a dynamic matrix over the same scalar field as A

Least common multiple of two integers.

See also

qpp::gcd()

Parameters

а	Integer
b	Integer

Returns

Least common multiple of a and b

Least common multiple of a list of integers.

See also

qpp::gcd()

Parameters

as List of integers

Returns

Least common multiple of all numbers in as

6.1.4.78 load()

Loads Eigen matrix from a binary file (internal format) in double precision.

See also

```
qpp::save()
```

The template parameter cannot be automatically deduced and must be explicitly provided, depending on the scalar field of the matrix that is being loaded.

Example:

```
// loads a previously saved Eigen dynamic complex matrix from "input.bin"
cmat mat = load<cmat>("input.bin");
```

Parameters

```
fname Output file name
```

6.1.4.79 loadMATLAB() [1/2]

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

```
qpp::saveMATLAB()
```

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen ket
// from the MATLAB file "input.mat"
ket psi = loadMATLAB<ket>("input.mat");
```

Template Parameters

Derived	Complex Eigen type
---------	--------------------

Parameters

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be loaded

Returns

Eigen dynamic matrix

6.1.4.80 loadMATLAB() [2/2]

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

qpp::saveMATLAB()

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen dynamic double matrix
// from the MATLAB file "input.mat"
dmat mat = loadMATLAB<dmat>("input.mat");
```

Template Parameters

Derived	Non-complex Eigen type
---------	------------------------

Parameters

most file MATALD most file		MATALB .mat file
ļ	mat_file	MATALD .mai me
	var_name	Variable name in the .mat file representing the matrix to be loaded

Returns

Eigen dynamic matrix

6.1.4.81 logdet()

Logarithm of the determinant.

Useful when the determinant overflows/underflows

Parameters

```
A Eigen expression
```

Returns

Logarithm of the determinant of A, as a scalar over the same scalar field as A

6.1.4.82 logm()

Matrix logarithm.

Parameters

```
A Eigen expression
```

Returns

Matrix logarithm of A

6.1.4.83 lognegativity() [1/2]

```
template<typename Derived >
double qpp::lognegativity (
```

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & dims )
```

Logarithmic negativity of the bi-partite mixed state A.

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Logarithmic negativity, with the logarithm in base 2

6.1.4.84 lognegativity() [2/2]

```
template<typename Derived > double qpp::lognegativity ( const Eigen::MatrixBase< Derived > & A, idx d = 2)
```

Logarithmic negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Logarithmic negativity, with the logarithm in base 2

6.1.4.85 marginalX()

Marginal distribution.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels
	the rows, Ylabels the columns)

Returns

Real vector consisting of the marginal distribution of X

6.1.4.86 marginalY()

Marginal distribution.

Parameters

probX\	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels
	the rows, Y labels the columns)

Returns

Real vector consisting of the marginal distribution of Y

Measures the state vector or density operator A using the set of Kraus operators Ks.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.4.88 measure() [2/9]

Measures the state vector or density matrix \boldsymbol{A} using the set of Kraus operators \boldsymbol{Ks} .

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.4.89 measure() [3/9]

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

Parameters

ſ	Α	Eigen expression	
	U	Unitary matrix whose columns represent the measurement basis vectors	

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.4.90 measure() [4/9]

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.4.91 measure() [5/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.4.92 measure() [6/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.4.93 measure() [7/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.4.94 measure() [8/9]

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

See also

```
qpp::measure_seq()
```

Note

The dimension of V must match the dimension of target. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression	
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors	
target	Subsystem indexes that are measured	
dims	Dimensions of the multi-partite system	

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

```
6.1.4.95 measure() [9/9]
```

Measures the part *target* of the multi-partite state vector or density matrix *A* in the orthonormal basis or rank-1 projectors specified by the columns of the matrix *V*.

See also

```
qpp::measure_seq()
```

Note

The dimension of *V* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression	
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors	
target	Subsystem indexes that are measured	
d	Subsystem dimensions	

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

```
6.1.4.96 measure_seq() [1/2]
```

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

See also

qpp::measure()

Α	Eigen expression
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

See also

qpp::measure()

Parameters

Α	Eigen expression
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|\text{mask}\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

Parameters

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

Returns

Multi-partite qudit state vector, as a complex dynamic column vector

```
6.1.4.99 mket() [2/2] ket qpp::mket ( const std::vector< idx > & mask, idx d = 2) [inline]
```

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Multi-partite qudit state vector, as a complex dynamic column vector

6.1.4.100 modinv()

Modular inverse of a mod p.

See also

```
qpp::egcd()
```

Note

a and p must be co-prime

Parameters

а	Non-negative integer
р	Non-negative integer

Returns

```
Modular inverse a^{-1} \mod p
```

6.1.4.101 modmul()

Modular multiplication without overflow.

Computes $ab \bmod p$ without overflow

Parameters

а	Integer
b	Integer
р	Positive integer

Returns

 $ab \bmod p$ avoiding overflow

6.1.4.102 modpow()

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

Note

Uses qpp::modmul() that avoids overflows

Computes $a^n \mod p$

Parameters

а	Non-negative integer
n	Non-negative integer
р	Strictly positive integer

Returns

```
a^n \bmod p
```

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

Parameters

I	mask	std::vector of non-negative integers
(dims	Dimensions of the multi-partite system

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

6.1.4.105 multiidx2n()

```
idx qpp::multiidx2n ( const \ std::vector < \ idx \ > \ \& \ midx, \\ const \ std::vector < \ idx \ > \ \& \ dims \ ) \quad [inline]
```

Multi-index to non-negative integer index.

See also

```
qpp::n2multiidx()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

Parameters

midx	Multi-index
dims	Dimensions of the multi-partite system

Returns

Non-negative integer index

6.1.4.106 n2multiidx()

Non-negative integer index to multi-index.

See also

qpp::multiidx2n()

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

Parameters

n	Non-negative integer index
dims	Dimensions of the multi-partite system

Returns

Multi-index of the same size as dims

6.1.4.107 negativity() [1/2]

Negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Negativity

6.1.4.108 negativity() [2/2]

```
template<typename Derived > double qpp::negativity ( const Eigen::MatrixBase< Derived > & A, idx d = 2)
```

Negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Negativity

6.1.4.109 norm()

Frobenius norm.

Parameters

```
A Eigen expression
```

Returns

Frobenius norm of A

6.1.4.110 normalize()

Normalizes state vector (column or row vector) or density matrix.

Parameters

```
A Eigen expression
```

Returns

Normalized state vector or density matrix

6.1.4.111 omega()

```
cplx qpp::omega (
        idx D ) [inline]
```

D-th root of unity.

```
D Non-negative integer
```

Returns

D-th root of unity $\exp(2\pi i/D)$

6.1.4.112 powm()

Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

See also

qpp::spectralpowm()

Explicitly multiplies the matrix ${\it A}$ with itself ${\it n}$ times. By convention ${\it A}^0={\it I}$.

Parameters

Α	Eigen expression
n	Non-negative integer

Returns

Matrix power A^n , as a dynamic matrix over the same scalar field as ${\it A}$

6.1.4.113 prj()

Projector.

Normalized projector onto state vector

Parameters

A Eigen expression

Returns

Projector onto the state vector *A*, or the matrix *Zero* if *A* has norm zero, as a dynamic matrix over the same scalar field as *A*

Element-wise product of A.

Parameters

```
A Eigen expression
```

Returns

Element-wise product of A, as a scalar over the same scalar field as A

Element-wise product of an STL-like range.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Element-wise product of the range, as a scalar over the same scalar field as the range

```
6.1.4.116 prod() [3/3]

template<typename Container >
Container::value_type qpp::prod (
```

```
const Container & c,
typename std::enable_if< is_iterable< Container >::value >::type * = nullptr )
```

Element-wise product of the elements of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Element-wise product of the elements of the container, as a scalar over the same scalar field as the container

Partial trace.

See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Returns

Partial trace $Tr_{subsys}(\cdot)$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

Partial trace.

See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial trace $Tr_{subsys}(\cdot)$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.4.119 ptrace1() [1/2]

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_A(\cdot)$ over the first subsystem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.4.120 ptrace1() [2/2]

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::ptrace1 (
```

```
const Eigen::MatrixBase< Derived > & A, idx d = 2)
```

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_A(\cdot)$ over the first subsytem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.4.121 ptrace2() [1/2]

Partial trace.

See also

qpp::ptrace1()

Partial trace over the second subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_B(\cdot)$ over the second subsytem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.4.122 ptrace2() [2/2]

Partial trace.

See also

```
qpp::ptrace1()
```

Partial trace over the second subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_B(\cdot)$ over the second subsytem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.4.123 ptranspose() [1/2]

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.4.124 ptranspose() [2/2]

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.4.125 QFT()

Qudit quantum Fourier transform.

Parameters

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Qudit quantum Fourier transform applied on A

6.1.4.126 qmutualinfo() [1/2]

```
template<typename Derived >
double qpp::qmutualinfo (
```

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & subsysA,
const std::vector< idx > & subsysB,
const std::vector< idx > & dims )
```

Quantum mutual information between 2 subsystems of a composite system.

Parameters

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
dims	Dimensions of the multi-partite system

Returns

Mutual information between the 2 subsystems

6.1.4.127 qmutualinfo() [2/2]

Quantum mutual information between 2 subsystems of a composite system.

Parameters

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
d	Subsystem dimensions

Returns

Mutual information between the 2 subsystems

Generates a random real number uniformly distributed in the interval [a, b)

а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Returns

Random real number (double) uniformly distributed in the interval [a, b)

Generates a random big integer uniformly distributed in the interval [a, b].

Note

To avoid ambiguity with double qpp::rand(double, double) cast at least one of the arguments to qpp::bigint

Parameters

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

Returns

Random big integer uniformly distributed in the interval [a, b]

Generates a random matrix with entries uniformly distributed in the interval [a,b)

If complex, then both real and imaginary parts are uniformly distributed in [a, b)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries uniformly distributed in [-1,1)
dmat mat = rand<dmat>(3, 3, -1, 1);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Returns

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd,
// with entries (both real and imaginary) uniformly distributed in [-1,1)
cmat mat = rand<cmat>(3, 3, -1, 1);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Returns

Random complex matrix

6.1.4.133 randH()

```
cmat qpp::randH (
    idx D = 2 ) [inline]
```

Generates a random Hermitian matrix.

Parameters

D Dimension of the Hilbert space

Returns

Random Hermitian matrix

6.1.4.134 randidx()

Generates a random index (idx) uniformly distributed in the interval [a, b].

Parameters

а	Beginning of the interval, belongs to it	
b	End of the interval, belongs to it	

Returns

Random index (idx) uniformly distributed in the interval [a, b]

6.1.4.135 randket()

```
ket qpp::randket (
    idx D = 2 ) [inline]
```

Generates a random normalized ket (pure state vector)

Parameters

```
D Dimension of the Hilbert space
```

Returns

Random normalized ket

6.1.4.136 randkraus()

```
std::vector<cmat> qpp::randkraus (
    idx N,
    idx D = 2 ) [inline]
```

Generates a set of random Kraus operators.

Note

The set of Kraus operators satisfy the closure condition $\sum_i K_i^\dagger K_i = I$

Parameters

Ν	Number of Kraus operators
D	Dimension of the Hilbert space

Returns

Set of N Kraus operators satisfying the closure condition

6.1.4.137 randn() [1/4]

```
template<typename Derived >
Derived qpp::randn (
    idx rows QPP_UNUSED_,
    idx cols QPP_UNUSED_,
    double mean QPP_UNUSED_ = 0,
    double sigma QPP_UNUSED_ = 1)
```

Generates a random matrix with entries normally distributed in N(mean, sigma)

If complex, then both real and imaginary parts are normally distributed in N(mean, sigma)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

```
6.1.4.138 randn() [2/4]

template<>
dmat qpp::randn (
         idx rows ,
         idx cols ,
         double mean ,
         double sigma ) [inline]
```

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries normally distributed in N(0,2)
dmat mat = randn<dmat>(3, 3, 0, 2);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Returns

Random real matrix

```
6.1.4.139 randn() [3/4]

template<>
cmat qpp::randn (
        idx rows ,
        idx cols ,
        double mean ,
        double sigma ) [inline]
```

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd, // with entries (both real and imaginary) normally distributed in N(0,2) cmat mat = randn<cmat>(3, 3, 0, 2);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Returns

Random complex matrix

Generates a random real number (double) normally distributed in N(mean, sigma)

Parameters

mean	Mean
sigma	Standard deviation

Returns

Random real number normally distributed in N(mean, sigma)

6.1.4.141 randperm()

```
std::vector<idx> qpp::randperm (
    idx N ) [inline]
```

Generates a random uniformly distributed permutation.

Uses Knuth shuffle method (as implemented by std::shuffle), so that all permutations are equally probable

Parameters

N Size of the permutation

Returns

Random permutation of size N

6.1.4.142 randprime()

Generates a random big prime uniformly distributed in the interval [a, b].

Parameters

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it
Ν	Maximum number of candidates

Returns

Random big integer uniformly distributed in the interval [a, b]

6.1.4.143 randprob()

```
std::vector<double> qpp::randprob (
    idx N ) [inline]
```

Generates a random probability vector uniformly distributed over the probability simplex.

Parameters

N Size of the probability vector

Returns

Random probability vector

6.1.4.144 randrho()

```
cmat qpp::randrho (
    idx D = 2 ) [inline]
```

Generates a random density matrix.

D Dimension of the Hilbert space

Returns

Random density matrix

6.1.4.145 randU()

```
cmat qpp::randU (
    idx D = 2 ) [inline]
```

Generates a random unitary matrix.

Parameters

D | Dimension of the Hilbert space

Returns

Random unitary

6.1.4.146 randV()

Generates a random isometry matrix.

Parameters

Din	Size of the input Hilbert space
Dout	Size of the output Hilbert space

Returns

Random isometry matrix

Renyi- α entropy of the density matrix A, for $\alpha \geq 0$.

double alpha)

Note

When $\alpha \to 1$ the Renyi entropy converges to the von-Neumann entropy, with the logarithm in base 2

Parameters

Α	Eigen expression
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

Returns

Renyi- α entropy, with the logarithm in base 2

Renyi- α entropy of the probability distribution *prob*, for $\alpha \geq 0$.

Note

When $\alpha \to 1$ the Renyi entropy converges to the Shannon entropy, with the logarithm in base 2

Parameters

prob	Real probability vector
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

Returns

Renyi- α entropy, with the logarithm in base 2

6.1.4.149 reshape()

Reshape.

Uses column-major order when reshaping (same as MATLAB)

Parameters

Α	Eigen expression
rows	Number of rows of the reshaped matrix
cols	Number of columns of the reshaped matrix

Returns

Reshaped matrix with rows rows and cols columns, as a dynamic matrix over the same scalar field as A

6.1.4.150 rho2bloch()

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

See also

qpp::bloch2rho()

Note

It is implicitly assumed that the density matrix is Hermitian

Parameters

```
A Eigen expression
```

Returns

3-dimensional Bloch vector

6.1.4.151 rho2pure()

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

Note

No purity check is done, the input state A must have rank one, otherwise the function returns the first non-zero eigenvector of A

Parameters

A Eigen expression, assumed to be proportional to a projector onto a pure state, i.e. A is assumed to have rank one

Returns

The unique non-zero eigenvector of A (up to a phase), as a dynamic column vector over the same scalar field as A

6.1.4.152 save()

Saves Eigen expression to a binary file (internal format) in double precision.

See also

qpp::load()

Parameters

Α	Eigen expression
fname	Output file name

6.1.4.153 saveMATLAB() [1/2]

```
template<typename Derived >
std::enable_if< std::is_same<typename Derived::Scalar, cplx>::value>::type qpp::saveMATLAB (
```

```
const Eigen::MatrixBase< Derived > & A,
const std::string & mat_file,
const std::string & var_name,
const std::string & mode )
```

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

```
qpp::loadMATLAB()
```

Template Parameters

Complex	Eigen type
---------	------------

Parameters

Α	Eigen expression over the complex field
mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be saved
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details

6.1.4.154 saveMATLAB() [2/2]

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

```
qpp::loadMATLAB()
```

Template Parameters

Npn-complex	Eigen type
-------------	------------

Parameters

Α	Non-complex Eigen expression
mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be saved
mode	Saving mode (append, overwrite etc.), see MATLAB <i>matOpen()</i> documentation for details

6.1.4.155 schatten()

Schatten matrix norm.

Parameters

Α	Eigen expression
р	Real number, greater or equal to 1, use qpp::infty for $p=\infty$

Returns

Schatten-p matrix norm of A

6.1.4.156 schmidtA() [1/2]

Schmidt basis on Alice side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix \boldsymbol{U} whose columns represent the Schmidt basis vectors on Alice side.

6.1.4.157 schmidtA() [2/2]

Schmidt basis on Alice side.

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix ${\cal U}$ whose columns represent the Schmidt basis vectors on Alice side.

Schmidt basis on Bob side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

Schmidt basis on Bob side.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

6.1.4.160 schmidtcoeffs() [1/2]

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.4.161 schmidtcoeffs() [2/2]

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Α	Eigen expression
d	Subsystem dimensions

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.4.162 schmidtprobs() [1/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.4.163 schmidtprobs() [2/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Α	Eigen expression
d	Subsystem dimensions

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.4.164 sigma()

Standard deviation.

Parameters

prob	Real probability vector representing the probability distribution of X
Χ	Real random variable values represented by an STL-like container

Returns

Standard deviation of X

6.1.4.165 sinm()

Matrix sin.

Parameters

A Eigen expression

Returns

Matrix sine of A

6.1.4.166 spectralpowm()

Matrix power.

See also

qpp::powm()

Uses the spectral decomposition of A to compute the matrix power. By convention $A^0 = I$.

Parameters

Α	Eigen expression
Z	Complex number

Returns

Matrix power A^z

6.1.4.167 sqrtm()

Matrix square root.

Parameters

```
A Eigen expression
```

Returns

Matrix square root of A

Element-wise sum of A.

```
A Eigen expression
```

Returns

Element-wise sum of A, as a scalar over the same scalar field as A

Element-wise sum of an STL-like range.

Parameters

	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Element-wise sum of the range, as a scalar over the same scalar field as the range

Element-wise sum of the elements of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Element-wise sum of the elements of the container, as a scalar over the same scalar field as the container

```
6.1.4.171 super2choi()
```

Converts superoperator matrix to Choi matrix.

See also

qpp::choi2super()

Parameters

A Superoperator matrix

Returns

Choi matrix

6.1.4.172 svals()

Singular values.

Parameters

A Eigen expression

Returns

Singular values of A, ordered in decreasing order, as a real dynamic column vector

6.1.4.173 svd()

Full singular value decomposition.

A Eigen expression

Returns

Tuple of: 1. Left sigular vectors of A, as columns of a complex dynamic matrix, 2. Singular values of A, ordered in decreasing order, as a real dynamic column vector, and 3. Right singular vectors of A, as columns of a complex dynamic matrix

6.1.4.174 svdU()

Left singular vectors.

Parameters

A Eigen expression

Returns

Complex dynamic matrix, whose columns are the left singular vectors of A

6.1.4.175 svdV()

Right singular vectors.

Parameters

A Eigen expression

Returns

Complex dynamic matrix, whose columns are the right singular vectors of A

6.1.4.176 syspermute() [1/2]

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Parameters

Α	Eigen expression
perm	Permutation
dims	Dimensions of the multi-partite system

Returns

Permuted system, as a dynamic matrix over the same scalar field as A

6.1.4.177 syspermute() [2/2]

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Parameters

Α	Eigen expression
perm	Permutation
d	Subsystem dimensions

Returns

Permuted system, as a dynamic matrix over the same scalar field as A

6.1.4.178 TFQ()

Inverse (adjoint) qudit quantum Fourier transform.

Parameters

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Inverse (adjoint) qudit quantum Fourier transform applied on A

6.1.4.179 trace()

Trace.

Parameters

```
A Eigen expression
```

Returns

Trace of A, as a scalar over the same scalar field as A

6.1.4.180 transpose()

Transpose.

A Eigen expression

Returns

Transpose of A, as a dynamic matrix over the same scalar field as A

```
6.1.4.181 tsallis() [1/2]  \begin{tabular}{ll} template < typename Derived > \\ double qpp::tsallis ( & const Eigen::MatrixBase < Derived > & A, \\ double $q$ ) \\ \end{tabular}
```

Tsallis- q entropy of the density matrix A, for $q \ge 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the von-Neumann entropy, with the logarithm in base e

Parameters

Α	Eigen expression
q	Non-negative real number

Returns

Tsallis- q entropy

Tsallis- q entropy of the probability distribution prob, for $q \geq 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the Shannon entropy, with the logarithm in base e

prob	Real probability vector
q	Non-negative real number

Returns

Tsallis- q entropy

6.1.4.183 uniform()

```
std::vector<double> qpp::uniform (
    idx N ) [inline]
```

Uniform probability distribution vector.

Parameters

N Size of the alphabet

Returns

Real vector consisting of a uniform distribution of size N

6.1.4.184 var()

Variance.

Parameters

prob	Real probability vector representing the probability distribution of X
X	Real random variable values represented by an STL-like container

Returns

Variance of X

6.1.4.185 x2contfrac()

Simple continued fraction expansion.

See also

qpp::contfrac2x()

Parameters

X	Real number
N	Maximum number of terms in the expansion
cut	Stop the expansion when the next term is greater than <i>cut</i>

Returns

Integer vector containing the simple continued fraction expansion of x. If there are M less than N terms in the expansion, a shorter vector with M components is returned.

6.1.5 Variable Documentation

6.1.5.1 chop

```
constexpr double qpp::chop = 1e-16
```

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

6.1.5.2 ee

```
constexpr double qpp::ee = 2.718281828459045235360287471352662497
```

Base of natural logarithm, e.

6.1.5.3 infty

```
constexpr double qpp::infty = std::numeric_limits<double>::max()
```

Used to denote infinity in double precision.

6.1.5.4 maxn

```
constexpr idx qpp::maxn = 64
```

Maximum number of allowed qubits/qudits (subsystems)

Used internally to allocate arrays on the stack (for performance reasons):

6.1.5.5 pi

```
constexpr double qpp::pi = 3.141592653589793238462643383279502884
```

 π

6.2 qpp::exception Namespace Reference

Quantum++ exception hierarchy namespace.

Classes

• class CustomException

Custom exception.

· class DimsInvalid

Invalid dimension(s) exception.

· class DimsMismatchCvector

Dimension(s) mismatch column vector size exception.

• class DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

· class DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

· class DimsMismatchVector

Dimension(s) mismatch vector size exception.

class DimsNotEqual

Dimensions not equal exception.

· class Duplicates

System (e.g. std::vector) has duplicates exception.

class Exception

Base class for generating Quantum++ custom exceptions.

· class InvalidIterator

Invalid iterator.

• class MatrixMismatchSubsys

Matrix mismatch subsystems exception.

• class MatrixNotCvector

Matrix is not a column vector exception.

class MatrixNotRvector

Matrix is not a row vector exception.

class MatrixNotSquare

Matrix is not square exception.

· class MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

class MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

· class MatrixNotSquareNorVector

Matrix is not square nor vector exception.

· class MatrixNotVector

Matrix is not a vector exception.

class NoCodeword

Codeword does not exist exception.

· class NotBipartite

Not bi-partite exception.

· class NotImplemented

Code not yet implemented.

class NotQubitCvector

Column vector is not 2 x 1 exception.

class NotQubitMatrix

Matrix is not 2 x 2 exception.

· class NotQubitRvector

Row vector is not 1 x 2 exception.

class NotQubitSubsys

Subsystems are not qubits exception.

class NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

class OutOfRange

Argument out of range exception.

class PermInvalid

Invalid permutation exception.

· class PermMismatchDims

Permutation mismatch dimensions exception.

class QuditAlreadyMeasured

Qudit was already measured exception.

· class SizeMismatch

Size mismatch exception.

· class SubsysMismatchDims

Subsystems mismatch dimensions exception.

class TypeMismatch

Type mismatch exception.

class UndefinedType

Not defined for this type exception.

• class Unknown

Unknown exception.

class ZeroSize

Object has zero size exception.

6.2.1 Detailed Description

Quantum++ exception hierarchy namespace.

6.3 qpp::experimental Namespace Reference

Experimental/test functions/classes, do not use or modify.

6.3.1 Detailed Description

Experimental/test functions/classes, do not use or modify.

6.4 qpp::internal Namespace Reference

Internal utility functions, do not use them directly or modify them.

Classes

- struct Display Impl
- class EqualEigen

Functor for comparing Eigen expressions for equality.

· class HashEigen

Functor for hashing Eigen expressions.

- class IOManipEigen
- class IOManipPointer
- · class IOManipRange
- · class Singleton

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Functions

```
    template < class T >
        void hash_combine (std::size_t &seed, const T &v)
```

Hash combine.

- void n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- template<typename Derived >

bool check_square_mat (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool check_vector (const Eigen::MatrixBase< Derived > &A)

• template<typename Derived >

bool check_rvector (const Eigen::MatrixBase< Derived > &A)

• template<typename Derived >

bool check_cvector (const Eigen::MatrixBase< Derived > &A)

• template<typename T >

bool check_nonzero_size (const T &x) noexcept

- template<typename T1 , typename T2 >

bool check_matching_sizes (const T1 &lhs, const T2 &rhs) noexcept

- bool check dims (const std::vector < idx > &dims)
- template<typename Derived >

 $bool\ check_dims_match_mat\ (const\ std::vector < idx > \&dims,\ const\ Eigen::MatrixBase < Derived > \&A)$

- template < typename Derived >
 bool check dims match cvect (const std::vector < idx > &dims, const Eigen::MatrixBase < Derived > &A)
- template<typename Derived >
 bool check_dims_match_rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)
- bool check_eq_dims (const std::vector < idx > &dims, idx dim) noexcept
- bool check_no_duplicates (std::vector< idx > v)
- bool check_subsys_match_dims (const std::vector < idx > &subsys, const std::vector < idx > &dims)
- template<typename Derived >
 bool check_qubit_matrix (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
 bool check_qubit_cvector (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
 bool check_qubit_rvector (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
 bool check_qubit_vector (const Eigen::MatrixBase< Derived > &A) noexcept
- bool check_perm (const std::vector< idx > &perm)
- template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > kron2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::
 MatrixBase< Derived2 > &B)
- template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > dirsum2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen
 ::MatrixBase< Derived2 > &B)
- template<typename T >
 void variadic_vector_emplace (std::vector< T > &)
- template<typename T , typename First , typename... Args> void variadic_vector_emplace (std::vector< T > &v, First &&first, Args &&... args)
- idx get_num_subsys (idx D, idx d)
- idx get_dim_subsys (idx sz, idx N)
- template<typename T, typename std::enable_if< std::numeric_limits< T >::is_iec559||is_complex< T >::value >::type * = nullptr>
 T abs_chop (const T &x, double chop=qpp::chop)
- template<typename T, typename std::enable_if<!(std::numeric_limits< T >::is_iec559||is_complex< T >::value)>::type * = nullptr>
 T abs_chop (const T &x, double QPP_UNUSED_ chop=qpp::chop)

6.4.1 Detailed Description

Internal utility functions, do not use them directly or modify them.

6.4.2 Function Documentation

6.4.2.1 abs_chop() [1/2]

```
6.4.2.2 abs_chop() [2/2]
\texttt{template} < \texttt{typename T , typename std::enable\_if} < ! (\texttt{std::numeric\_limits} < \texttt{T} > :: \texttt{is\_iec559} | \texttt{is\_} \leftarrow \texttt{typename T} | \texttt{type
complex< T >::value)>::type * = nullptr>
T qpp::internal::abs_chop (
                                                const T & x,
                                                  double QPP_UNUSED_ chop = qpp::chop )
6.4.2.3 check_cvector()
template<typename Derived >
bool qpp::internal::check_cvector (
                                                 const Eigen::MatrixBase< Derived > & A )
6.4.2.4 check_dims()
bool qpp::internal::check_dims (
                                                const std::vector< idx > & dims ) [inline]
6.4.2.5 check_dims_match_cvect()
template<typename Derived >
bool qpp::internal::check_dims_match_cvect (
                                               const std::vector< idx > & dims,
                                                const Eigen::MatrixBase< Derived > & A )
6.4.2.6 check_dims_match_mat()
{\tt template}{<}{\tt typename \ Derived} >
bool qpp::internal::check_dims_match_mat (
                                               const std::vector< idx > & dims,
                                                 const Eigen::MatrixBase< Derived > & A )
6.4.2.7 check_dims_match_rvect()
template<typename Derived >
bool qpp::internal::check\_dims\_match\_rvect (
                                                 const std::vector< idx > & dims,
                                                  const Eigen::MatrixBase< Derived > & A )
```

6.4.2.8 check_eq_dims()

6.4.2.9 check_matching_sizes()

6.4.2.10 check_no_duplicates()

```
bool qpp::internal::check_no_duplicates ( std::vector < \ idx \ > \ v \ ) \quad [inline]
```

6.4.2.11 check_nonzero_size()

6.4.2.12 check_perm()

```
bool qpp::internal::check_perm (  \mbox{const std::vector} < \mbox{idx} \ > \mbox{\& perm} \ ) \quad \mbox{[inline]}
```

6.4.2.13 check_qubit_cvector()

```
6.4.2.14 check_qubit_matrix()
```

```
template<typename Derived >
bool qpp::internal::check_qubit_matrix (
             const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.15 check_qubit_rvector()
template<typename Derived >
bool qpp::internal::check_qubit_rvector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.16 check_qubit_vector()
template<typename Derived >
bool qpp::internal::check_qubit_vector (
             const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.17 check_rvector()
template<typename Derived >
bool qpp::internal::check_rvector (
             const Eigen::MatrixBase< Derived > & A )
6.4.2.18 check_square_mat()
template<typename Derived >
bool qpp::internal::check\_square\_mat (
             const Eigen::MatrixBase< Derived > & A )
6.4.2.19 check_subsys_match_dims()
bool qpp::internal::check_subsys_match_dims (
            const std::vector< idx > & subsys,
             const std::vector< idx > & dims ) [inline]
```

6.4.2.20 check_vector()

6.4.2.21 dirsum2()


6.4.2.22 get_dim_subsys()

6.4.2.23 get_num_subsys()

6.4.2.24 hash_combine()

Hash combine.

Template Parameters



Parameters

seed Initial seed, will be updated by the function

Value with which the hash is combined

```
6.4.2.25 kron2()
```

6.4.2.26 multiidx2n()

6.4.2.27 n2multiidx()

6.4.2.28 variadic_vector_emplace() [1/2]

```
template<typename T > void qpp::internal::variadic_vector_emplace ( std::vector < T \,>\, \& \quad )
```

6.4.2.29 variadic_vector_emplace() [2/2]

6.5 qpp::literals Namespace Reference

Functions

```
• constexpr cplx operator"" _i (unsigned long long int x) noexcept
      User-defined literal for complex i = \sqrt{-1} (integer overload)
• constexpr cplx operator"" _i (long double x) noexcept
      User-defined literal for complex i = \sqrt{-1} (real overload)

    constexpr std::complex< float > operator""_if (unsigned long long int x) noexcept

      User-defined literal for complex i = \sqrt{-1} (integer overload)
• constexpr std::complex< float > operator"" _if (long double x) noexcept
      User-defined literal for complex i = \sqrt{-1} (real overload)
• template<char... Bits>
  ket operator"" _ket ()
      Multi-partite qubit ket user-defined literal.
• template<char... Bits>
  bra operator"" _bra ()
      Multi-partite qubit bra user-defined literal.
• template<char... Bits>
  cmat operator"" _prj ()
      Multi-partite qubit projector user-defined literal.
```

6.5.1 Function Documentation

```
6.5.1.1 operator"""_bra()

template<char... Bits>
bra qpp::literals::operator"" _bra ( )
```

Multi-partite qubit bra user-defined literal.

See also

```
qpp::mket() and qpp::adjoint()
```

Constructs the multi-partite qubit bra $\langle Bits |$

Template Parameters

Bits String of binary numbers representing the qubit bra

Returns

Multi-partite qubit bra, as a complex dynamic row vector

```
6.5.1.2 operator""" _i() [1/2]
constexpr cplx qpp::literals::operator"" _i (
               unsigned long long int x ) [inline], [noexcept]
User-defined literal for complex i = \sqrt{-1} (integer overload)
Example:
cplx z = 4_i; // type of z is std::complex<double>
6.5.1.3 operator""" _i() [2/2]
constexpr cplx qpp::literals::operator"" _i (
               long double x ) [inline], [noexcept]
User-defined literal for complex i = \sqrt{-1} (real overload)
Example:
cplx z = 4.5_i; // type of z is std::complex<double>
6.5.1.4 operator""" _if() [1/2]
constexpr std::complex<float> qpp::literals::operator"" _if (
               unsigned long long int x ) [inline], [noexcept]
User-defined literal for complex i = \sqrt{-1} (integer overload)
Example:
auto z = 4_if; // type of z is std::complex<double>
6.5.1.5 operator"""_if() [2/2]
constexpr std::complex<float> qpp::literals::operator"" _if (
               long double x ) [inline], [noexcept]
User-defined literal for complex i = \sqrt{-1} (real overload)
Example:
auto z = 4.5_{if}; // type of z is std::complex<float>
6.5.1.6 operator""" _ket()
template<char... Bits>
{\color{red} \texttt{ket} \ \textit{qpp::literals::operator""} \ \_\texttt{ket} \ (\ )}
Multi-partite qubit ket user-defined literal.
See also
     qpp::mket()
Constructs the multi-partite qubit ket |Bits>
```

Template Parameters

Bits	String of binary numbers representing the qubit ket	
------	---	--

Returns

Multi-partite qubit ket, as a complex dynamic column vector

```
6.5.1.7 operator"""_prj()

template<char... Bits>
cmat qpp::literals::operator"" _prj ( )
```

Multi-partite qubit projector user-defined literal.

See also

qpp::mprj()

Constructs the multi-partite qubit projector $|Bits\rangle\langle Bits|$ (in the computational basis)

Template Parameters

Bits String of binary numbers representing the qubit state to project on

Returns

Multi-partite qubit projector, as a complex dynamic matrix

Chapter 7

Class Documentation

7.1 qpp::Bit_circuit Class Reference


Classical reversible circuit simulator.

#include <classes/reversible.h>

Inheritance diagram for qpp::Bit_circuit:



Collaboration diagram for qpp::Bit_circuit:



Public Member Functions

• Bit_circuit (idx n)

Constructs a bit circuit instance.

• Bit_circuit (const Dynamic_bitset &dynamic_bitset)

Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.

Bit_circuit & X (idx i)

Bit flip.

virtual ∼Bit_circuit ()=default

Default virtual destructor.

• Bit_circuit & NOT (idx i)

Bit flip.

Bit_circuit & CNOT (idx ctrl, idx target)

Controlled-NOT.

• Bit_circuit & TOF (idx i, idx j, idx k)

Toffoli gate.

• Bit_circuit & SWAP (idx i, idx j)

Swap bits.

• Bit_circuit & FRED (idx i, idx j, idx k)

Fredkin gate (Controlled-SWAP)

Bit_circuit & reset () noexcept

Reset the circuit all zero, clear all gates.

- idx get_gate_count (const std::string &name={}) const Bit circuit gate count.
- idx get_gate_depth (const std::string &name={}) const

Bit circuit gate depth.

Private Attributes

- std::unordered_map< std::string, idx > depth_ {}
 gate depths
- Dynamic_bitset bNOT_
- Dynamic_bitset bCNOT_
- Dynamic_bitset bSWAP_
- Dynamic_bitset bTOF_
- Dynamic_bitset bFRED_
- Dynamic_bitset btotal_

used for depth calculations

Additional Inherited Members

7.1.1 Detailed Description

Classical reversible circuit simulator.

7.1.2 Constructor & Destructor Documentation

```
7.1.2.1 Bit_circuit() [1/2]

qpp::Bit_circuit::Bit_circuit (
        idx n ) [inline], [explicit]
```

Constructs a bit circuit instance.

Parameters

n Number of classical bits

Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.

Parameters

```
dynamic_bitset Dynamic bitset
```

```
7.1.2.3 ∼Bit_circuit()
```

```
virtual qpp::Bit_circuit::~Bit_circuit ( ) [virtual], [default]
```

Default virtual destructor.

7.1.3 Member Function Documentation

7.1.3.1 CNOT()

Controlled-NOT.

Parameters

ctrl	Control bit index
target	Target bit index

Returns

Reference to the current instance

7.1.3.2 FRED()

```
Bit_circuit& qpp::Bit_circuit::FRED (
    idx i,
    idx j,
    idx k) [inline]
```

Fredkin gate (Controlled-SWAP)

i	Control bit index	
j	Target first bit index	
k	Target second bit index	

Returns

Reference to the current instance

7.1.3.3 get_gate_count()

Bit circuit gate count.

Note

If name is empty (default), returns the total gate count of the circuit

Parameters

name	Gate name (optional). Possible names are NOT (X), CNOT, SWAP, TOF, FRED.
------	--

Returns

Gate count

7.1.3.4 get_gate_depth()

Bit circuit gate depth.

Note

If name is empty (default), returns the total gate depth of the circuit

Parameters

name	Gate name (optional). Possible names are NOT (X), CNOT, SWAP, TOF, FRED.

```
Returns
```

Gate depth

```
7.1.3.5 NOT()
```

```
Bit_circuit& qpp::Bit_circuit::NOT (
        idx i ) [inline]
```

Bit flip.

See also

```
qpp::Bit_circuit::X()
```

Parameters

```
i Bit position in the circuit
```

Returns

Reference to the current instance

```
7.1.3.6 reset()
```

```
Bit_circuit& qpp::Bit_circuit::reset ( ) [inline], [noexcept]
```

Reset the circuit all zero, clear all gates.

Returns

Reference to the current instance

7.1.3.7 SWAP()

```
Bit_circuit& qpp::Bit_circuit::SWAP (
        idx i,
        idx j) [inline]
```

Swap bits.

i	Bit index
j	Bit index

Returns

Reference to the current instance

7.1.3.8 TOF()

```
Bit_circuit& qpp::Bit_circuit::TOF (
    idx i,
    idx j,
    idx k) [inline]
```

Toffoli gate.

Parameters

i	Control first bit index
j	Control second bit index
k	Target bit index

Returns

Reference to the current instance

7.1.3.9 X()

```
Bit_circuit@ qpp::Bit_circuit::X (
        idx i ) [inline]
```

Bit flip.

See also

```
qpp::Bit_circuit::NOT()
```

Parameters

i Bit position in the circuit

Returns

Reference to the current instance

7.1.4 Member Data Documentation

```
7.1.4.1 bCNOT_
Dynamic_bitset qpp::Bit_circuit::bCNOT_ [private]
7.1.4.2 bFRED_
Dynamic_bitset qpp::Bit_circuit::bFRED_ [private]
7.1.4.3 bNOT_
Dynamic_bitset qpp::Bit_circuit::bNOT_ [private]
7.1.4.4 bSWAP_
Dynamic_bitset qpp::Bit_circuit::bSWAP_ [private]
7.1.4.5 bTOF_
Dynamic_bitset qpp::Bit_circuit::bTOF_ [private]
7.1.4.6 btotal_
Dynamic_bitset qpp::Bit_circuit::btotal_ [private]
used for depth calculations
```

```
7.1.4.7 count_
```

```
std::unordered_map<std::string, idx> qpp::Bit_circuit::count_ {} [private]
gate counts
```

7.1.4.8 depth_

```
std::unordered_map<std::string, idx> qpp::Bit_circuit::depth_ {} [private]
gate depths
```

The documentation for this class was generated from the following file:


· classes/reversible.h

7.2 qpp::Codes Class Reference


const Singleton class that defines quantum error correcting codes

```
#include <classes/codes.h>
```

Inheritance diagram for qpp::Codes:



Collaboration diagram for qpp::Codes:



Public Types

enum Type { Type::FIVE_QUBIT, Type::SEVEN_QUBIT_STEANE, Type::NINE_QUBIT_SHOR }
 Code types, add more codes here if needed.

Public Member Functions

ket codeword (Type type, idx i) const
 Returns the codeword of the specified code type.

Private Member Functions

• Codes ()

Default constructor.

∼Codes ()=default

Default destructor.

Friends

class internal::Singleton < const Codes >

Additional Inherited Members

7.2.1 Detailed Description

const Singleton class that defines quantum error correcting codes

7.2.2 Member Enumeration Documentation

7.2.2.1 Type

```
enum qpp::Codes::Type [strong]
```

Code types, add more codes here if needed.

See also

qpp::Codes::codeword()

Enumerator

FIVE_QUBIT	[[5,1,3]] qubit code
SEVEN_QUBIT_STEANE	[[7,1,3]] Steane qubit code
NINE_QUBIT_SHOR	[[9,1,3]] Shor qubit code

7.2.3 Constructor & Destructor Documentation

7.2.3.1 Codes()

```
qpp::Codes::Codes ( ) [inline], [private]
```

Default constructor.

7.2.3.2 ∼Codes()

```
qpp::Codes::~Codes ( ) [private], [default]
```

Default destructor.

7.2.4 Member Function Documentation

7.2.4.1 codeword()

Returns the codeword of the specified code type.

See also

```
qpp::Codes::Type
```

Parameters

type	Code type
i	Codeword index

Returns

i-th codeword of the code type

7.2.5 Friends And Related Function Documentation

7.2.5.1 internal::Singleton < const Codes >

```
friend class internal::Singleton< const Codes > [friend]
```

The documentation for this class was generated from the following file:


· classes/codes.h

7.3 qpp::exception::CustomException Class Reference

Custom exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::CustomException:



Collaboration diagram for qpp::exception::CustomException:



Public Member Functions

• CustomException (const std::string &where, const std::string &what)

Private Member Functions

• std::string description () const override Exception description.

Private Attributes

std::string what_{{}}

7.3.1 Detailed Description

Custom exception.

Custom exception, the user must provide a custom message

7.3.2 Constructor & Destructor Documentation

7.3.2.1 CustomException()

7.3.3 Member Function Documentation

7.3.3.1 description()

```
std::string qpp::exception::CustomException::description ( ) const [inline], [override],
[private], [virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.3.4 Member Data Documentation

7.3.4.1 what_

```
std::string qpp::exception::CustomException::what_ {} [private]
```

The documentation for this class was generated from the following file:


· classes/exception.h

7.4 qpp::exception::DimsInvalid Class Reference

Invalid dimension(s) exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsInvalid:



Collaboration diagram for qpp::exception::DimsInvalid:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.4.1 Detailed Description

Invalid dimension(s) exception.

std::vector<idx> of dimensions has zero size or contains zeros

7.4.2 Member Function Documentation

7.4.2.1 description()

std::string qpp::exception::DimsInvalid::description () const [inline], [override], [virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.4.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

The documentation for this class was generated from the following file:

· classes/exception.h

7.5 qpp::exception::DimsMismatchCvector Class Reference


Dimension(s) mismatch column vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchCvector:



Collaboration diagram for qpp::exception::DimsMismatchCvector:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.5.1 Detailed Description

Dimension(s) mismatch column vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a column vector)

7.5.2 Member Function Documentation

7.5.2.1 description()

std::string qpp::exception::DimsMismatchCvector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.5.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
WITCIC	Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.6 qpp::exception::DimsMismatchMatrix Class Reference


Dimension(s) mismatch matrix size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchMatrix:



Collaboration diagram for qpp::exception::DimsMismatchMatrix:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.6.1 Detailed Description

Dimension(s) mismatch matrix size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of rows of the Eigen::Matrix (assumed to be a square matrix)

7.6.2 Member Function Documentation

7.6.2.1 description()

```
std::string qpp::exception::DimsMismatchMatrix::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.6.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.7 qpp::exception::DimsMismatchRvector Class Reference


Dimension(s) mismatch row vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchRvector:



Collaboration diagram for qpp::exception::DimsMismatchRvector:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.7.1 Detailed Description

Dimension(s) mismatch row vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row vector)

7.7.2 Member Function Documentation

7.7.2.1 description()

std::string qpp::exception::DimsMismatchRvector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.7.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.8 qpp::exception::DimsMismatchVector Class Reference


Dimension(s) mismatch vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchVector:



Collaboration diagram for qpp::exception::DimsMismatchVector:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.8.1 Detailed Description

Dimension(s) mismatch vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row/column vector)

7.8.2 Member Function Documentation

7.8.2.1 description()

```
std::string qpp::exception::DimsMismatchVector::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.8.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


classes/exception.h

7.9 qpp::exception::DimsNotEqual Class Reference


Dimensions not equal exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsNotEqual:



Collaboration diagram for qpp::exception::DimsNotEqual:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.9.1 Detailed Description

Dimensions not equal exception.

Local/global dimensions are not equal

7.9.2 Member Function Documentation

7.9.2.1 description()

std::string qpp::exception::DimsNotEqual::description () const [inline], [override], [virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.9.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred


The documentation for this class was generated from the following file:

· classes/exception.h

7.10 qpp::internal::Display_Impl_ Struct Reference

```
#include <internal/util.h>
```

Inheritance diagram for qpp::internal::Display_Impl_:



Public Member Functions

template<typename T >
 std::ostream & display_impl_ (const T &A, std::ostream &os, double chop=qpp::chop) const

7.10.1 Member Function Documentation

7.10.1.1 display_impl_()

The documentation for this struct was generated from the following file:


• internal/util.h

7.11 qpp::exception::Duplicates Class Reference


System (e.g. std::vector) has duplicates exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Duplicates:



Collaboration diagram for qpp::exception::Duplicates:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.11.1 Detailed Description

System (e.g. std::vector) has duplicates exception.

7.11.2 Member Function Documentation

7.11.2.1 description()

```
std::string qpp::exception::Duplicates::description ( ) const [inline], [override], [virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.11.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.12 qpp::Dynamic_bitset Class Reference


Dynamic bitset class, allows the specification of the number of bits at runtime.

#include <classes/reversible.h>

Inheritance diagram for qpp::Dynamic_bitset:



Collaboration diagram for qpp::Dynamic_bitset:



Public Types

- using value_type = unsigned int type of the storage elements
- using storage_type = std::vector< value_type > type of the storage

Public Member Functions

• Dynamic_bitset (idx n)

Constructor, initializes all bits to false (zero)

virtual ~Dynamic_bitset ()=default

Default virtual destructor.

const storage_type & data () const

Raw storage space of the bitset.

idx size () const noexcept

Number of bits stored in the bitset.

• idx storage_size () const noexcept

Size of the underlying storage space (in units of value_type, unsigned int by default)

· idx count () const noexcept

Number of bits set to one in the bitset (Hamming weight)

· bool get (idx pos) const noexcept

The value of the bit at position pos.

• bool none () const noexcept

Checks whether none of the bits are set.

• bool all () const noexcept

Checks whether all bits are set.

· bool any () const noexcept

Checks whether any bit is set.

Dynamic_bitset & set (idx pos, bool value=true)

Sets the bit at position pos.

• Dynamic_bitset & set () noexcept

Set all bits to true.

Dynamic_bitset & rand (idx pos, double p=0.5)

Sets the bit at position pos according to a Bernoulli(p) distribution.

Dynamic_bitset & rand (double p=0.5)

Sets all bits according to a Bernoulli(p) distribution.

• Dynamic_bitset & reset (idx pos)

Sets the bit at position pos to false.

• Dynamic_bitset & reset () noexcept

Sets all bits to false.

• Dynamic_bitset & flip (idx pos)

Flips the bit at position pos.

Dynamic_bitset & flip () noexcept

Flips all bits.

bool operator== (const Dynamic_bitset &rhs) const noexcept

Equality operator.

bool operator!= (const Dynamic_bitset &rhs) const noexcept

Inequality operator.

idx operator- (const Dynamic_bitset &rhs) const noexcept

Number of places the two bitsets differ (Hamming distance)

template < class CharT = char, class Traits = std::char_traits < CharT>, class Allocator = std::allocator < CharT>> std::basic_string < CharT, Traits, Allocator > to_string (CharT zero=CharT('0'), CharT one=CharT('1')) const String representation.

Protected Member Functions

• idx index_ (idx pos) const

Index of the pos bit in the storage space.

idx offset_ (idx pos) const

Offset of the pos bit in the storage space relative to its index.

Protected Attributes

```
    idx storage_size_
        storage size
    idx n_
        number of bits
    std::vector < value_type > v_
        storage space
```

Private Member Functions

7.12.1 Detailed Description

Dynamic bitset class, allows the specification of the number of bits at runtime.

Note

The interface mimics std::bitset<>

7.12.2 Member Typedef Documentation

```
7.12.2.1 storage_type
using qpp::Dynamic_bitset::storage_type = std::vector<value_type>
type of the storage

7.12.2.2 value_type
using qpp::Dynamic_bitset::value_type = unsigned int
type of the storage elements
```

7.12.3 Constructor & Destructor Documentation

```
7.12.3.1 Dynamic_bitset()
```

```
qpp::Dynamic_bitset::Dynamic_bitset (
          idx n ) [inline], [explicit]
```

Constructor, initializes all bits to false (zero)

Parameters

n Number of bits in the bitset

```
7.12.3.2 ~Dynamic_bitset()
```

```
virtual qpp::Dynamic_bitset::~Dynamic_bitset ( ) [virtual], [default]
```

Default virtual destructor.

7.12.4 Member Function Documentation

```
7.12.4.1 all()
```

```
bool qpp::Dynamic_bitset::all ( ) const [inline], [noexcept]
```

Checks whether all bits are set.

Returns

True if all of the bits are set

7.12.4.2 any()

```
bool qpp::Dynamic_bitset::any ( ) const [inline], [noexcept]
```

Checks whether any bit is set.

Returns

True if any of the bits is set

7.12.4.3 count()

```
idx qpp::Dynamic_bitset::count ( ) const [inline], [noexcept]
```

Number of bits set to one in the bitset (Hamming weight)

Returns

Hamming weight

7.12.4.4 data()

```
const storage_type& qpp::Dynamic_bitset::data ( ) const [inline]
```

Raw storage space of the bitset.

Returns

Const reference to the underlying storage space

7.12.4.5 display()

qpp::IDisplay::display() override, displays the bitset bit by bit

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.12.4.6 flip() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip (
        idx pos ) [inline]
```

Flips the bit at position pos.

Parameters

pos Position in the bitset

Returns

Reference to the current instance

```
7.12.4.7 flip() [2/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip ( ) [inline], [noexcept]
```

Flips all bits.

Returns

Reference to the current instance

7.12.4.8 get()

```
bool qpp::Dynamic_bitset::get (
          idx pos ) const [inline], [noexcept]
```

The value of the bit at position pos.

Parameters

pos Position in the bitset

Returns

The value of the bit at position pos

7.12.4.9 index_()

Index of the pos bit in the storage space.

Parameters

```
pos Bit location
```

Returns

Index of the pos bit in the storage space

7.12.4.10 none()

```
bool qpp::Dynamic_bitset::none ( ) const [inline], [noexcept]
```

Checks whether none of the bits are set.

Returns

True if none of the bits are set

7.12.4.11 offset_()

Offset of the pos bit in the storage space relative to its index.

Parameters

```
pos Bit location
```

Returns

Offset of the pos bit in the storage space relative to its index

7.12.4.12 operator"!=()

Inequality operator.

Parameters

```
rhs Dynamic_bitset against which the inequality is being tested
```

Returns

True if the bitsets are not equal (bit by bit), false otherwise

7.12.4.13 operator-()

Number of places the two bitsets differ (Hamming distance)

Parameters

rhs Dynamic_bitset against which the Hamming distance is computed

Returns

Hamming distance

7.12.4.14 operator==()

Equality operator.

Parameters

```
rhs Dynamic_bitset against which the equality is being tested
```

Returns

True if the bitsets are equal (bit by bit), false otherwise

7.12.4.15 rand() [1/2]

```
Dynamic_bitset& qpp::Dynamic_bitset::rand (
    idx pos,
    double p = 0.5 ) [inline]
```

Sets the bit at position *pos* according to a Bernoulli(p) distribution.

Parameters

pos	Position in the bitset
р	Probability

Returns

Reference to the current instance

Sets all bits according to a Bernoulli(p) distribution.

Parameters

```
p Probability
```

Returns

Reference to the current instance

Sets the bit at position pos to false.

Parameters

pos Position in the bitset	
----------------------------	--

Returns

Reference to the current instance

```
7.12.4.18 reset() [2/2]
Dynamic_bitset& qpp::Dynamic_bitset::reset ( ) [inline], [noexcept]
Sets all bits to false.
```

Returns

Reference to the current instance

```
7.12.4.19 set() [1/2]
```

Sets the bit at position pos.

Parameters

pos	Position in the bitset
value	Bit value

Returns

Reference to the current instance

```
7.12.4.20 set() [2/2]

Dynamic_bitset& qpp::Dynamic_bitset::set () [inline], [noexcept]
```

Set all bits to true.

Returns

Reference to the current instance

```
7.12.4.21 size()
```

```
idx qpp::Dynamic_bitset::size ( ) const [inline], [noexcept]
```

Number of bits stored in the bitset.

Returns

Number of bits stored in the bitset

```
7.12.4.22 storage_size()
```

```
idx qpp::Dynamic_bitset::storage_size ( ) const [inline], [noexcept]
```

Size of the underlying storage space (in units of value_type, unsigned int by default)

Returns

Size of the underlying storage space

7.12.4.23 to_string()

String representation.

Template Parameters

CharT	String character type
Traits	String traits
Allocator	String Allocator

Parameters

	Character representing the zero
one	Character representing the one

Returns

The bitset as a string

7.12.5 Member Data Documentation

```
7.12.5.1 n_
idx qpp::Dynamic_bitset::n_ [protected]
```

7.12.5.2 storage_size_

number of bits

```
idx qpp::Dynamic_bitset::storage_size_ [protected]
```

storage size

```
7.12.5.3 v_
std::vector<value_type> qpp::Dynamic_bitset::v_ [protected]
storage space
```

The documentation for this class was generated from the following file:

· classes/reversible.h

7.13 qpp::internal::EqualEigen Class Reference

Functor for comparing Eigen expressions for equality.

```
#include <functions.h>
```

Public Member Functions

template<typename Derived >
 bool operator() (const Eigen::MatrixBase< Derived > &A, const Eigen::MatrixBase< Derived > &B) const

7.13.1 Detailed Description

Functor for comparing Eigen expressions for equality.

Note

Works without assertion fails even if the dimensions of the arguments are different (in which case simply returns false

7.13.2 Member Function Documentation

7.13.2.1 operator()()

The documentation for this class was generated from the following file:


· functions.h

7.14 qpp::exception::Exception Class Reference


Base class for generating Quantum++ custom exceptions.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Exception:



Collaboration diagram for qpp::exception::Exception:



Public Member Functions

- Exception (const std::string &where)
 - Constructs an exception.
- const char * what () const noexcept override
 - Overrides std::exception::what()
- virtual std::string description () const =0
 - Exception description.

Private Attributes

- std::string where_
- std::string msg_

7.14.1 Detailed Description

Base class for generating Quantum++ custom exceptions.

Derive from this class if more exceptions are needed, making sure to override qpp::exception::Exception::Exception::description() in the derived class and to inherit the constructor qpp::exception::Exception::Exception(). Preferably keep your newly defined exception classes in the namespace qpp::exception.

Example:

```
namespace qpp
{
namespace exception
{
    class ZeroSize : public Exception
    {
        public:
            std::string description() const override
            {
                  return "Object has zero size";
            }
            // inherit the base class' qpp::exception::Exception constructor
            using Exception::Exception;
        };
} // namespace exception
} // namespace qpp
```

7.14.2 Constructor & Destructor Documentation

7.14.2.1 Exception()

Constructs an exception.

Parameters

where Text representing where the exception occurred

qpp::exception::ZeroSize, and qpp::exception::Unknown.

7.14.3 Member Function Documentation

7.14.3.1 description()

```
std::string qpp::exception::Exception::description ( ) const [inline], [pure virtual]
Exception description.
```

Returns

Exception description

Implemented in qpp::exception::InvalidIterator, qpp::exception::NotImplemented, qpp::exception::CustomException, qpp::exception::Duplicates, qpp::exception::QuditAlreadyMeasured, qpp::exception::UndefinedType, qpp::exception::SizeMismatch, qpp::exception::TypeMismatch, qpp::exception::OutOfRange, qpp::exception::NotOdeword, qpp::exception::NotBipartite, qpp::exception::NotQubitSubsys, qpp::exception::NotQubitVector, qpp::exception::NotQubitRvector, qpp::exception::NotQubitCvector qpp::exception::NotQubitMatrix, qpp::exception::PermMismatchDims, qpp::exception::PermInvalid, qpp::exception::SubsysMismatchEqpp::exception::DimsMismatchVector, qpp::exception::DimsMismatchCvector, qpp::exception::DimsMismatchMatrix, qpp::exception::DimsNotEqual, qpp::exception::DimsInvalid, qpp::exception::MatrixMismatchSupp::exception::MatrixNotSquareNorVector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::MatrixNotSquareNo

7.14.3.2 what()

```
const char* qpp::exception::Exception::what ( ) const [inline], [override], [noexcept]
```

Overrides std::exception::what()

Returns

Exception description

7.14.4 Member Data Documentation

7.14.4.1 msg_

```
std::string qpp::exception::Exception::msg_ [mutable], [private]
```

7.14.4.2 where_

```
std::string qpp::exception::Exception::where_ [private]
```

The documentation for this class was generated from the following file:


· classes/exception.h

7.15 qpp::Gates Class Reference


const Singleton class that implements most commonly used gates

```
#include <classes/gates.h>
```

Inheritance diagram for qpp::Gates:



Collaboration diagram for qpp::Gates:



Public Member Functions

cmat Rn (double theta, const std::vector< double > &n) const

Qubit rotation of theta about the 3-dimensional real (unit) vector n. cmat RX (double theta) const

Qubit rotation of theta about the X axis.

· cmat RY (double theta) const

Qubit rotation of theta about the Y axis.

cmat RZ (double theta) const

Qubit rotation of theta about the Z axis.

• cmat Zd (idx D=2) const

Generalized Z gate for qudits.

cmat SWAPd (idx D=2) const

SWAP gate for qudits.

cmat Fd (idx D=2) const

Quantum Fourier transform gate for qudits.

cmat MODMUL (idx a, idx N, idx n) const

Modular multiplication gate for qubits Implements $|x\rangle \longrightarrow |ax \bmod N\rangle$.

• cmat Xd (idx D=2) const

Generalized X gate for qudits.

• template<typename Derived = Eigen::MatrixXcd>

Derived Id (idx D=2) const

Identity gate.

template<typename Derived >

dyn_mat< typename Derived::Scalar > CTRL (const Eigen::MatrixBase< Derived > &A, const std::vector idx > &ctrl, const std::vector < idx > &target, idx n, idx d=2) const

Generates the multi-partite multiple-controlled-A gate in matrix form.

template<typename Derived >

dyn mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const std::vector< idx > &dims) const

Expands out.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const std::initializer list< idx > &dims) const

Expands out.

```
• template<typename Derived >
       dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, idx n,
       idx d=2) const
          Expands out.

    std::string get_name (const cmat &U) const

          Get the name of the most common qubit gates.
Public Attributes
    • cmat Id2 {cmat::Identity(2, 2)}
          Identity gate.

    cmat H {cmat::Zero(2, 2)}

          Hadamard gate.

    cmat X {cmat::Zero(2, 2)}

          Pauli Sigma-X gate.

    cmat Y {cmat::Zero(2, 2)}

          Pauli Sigma-Y gate.

    cmat Z {cmat::Zero(2, 2)}

          Pauli Sigma-Z gate.

    cmat S {cmat::Zero(2, 2)}

          S gate.
    cmat T {cmat::Zero(2, 2)}
           T gate.

    cmat CNOT {cmat::Identity(4, 4)}

          Controlled-NOT control target gate.

    cmat CZ {cmat::Identity(4, 4)}

          Controlled-Phase gate.
    • cmat CNOTba {cmat::Zero(4, 4)}
          Controlled-NOT target->control gate.
    • cmat SWAP {cmat::Identity(4, 4)}
          SWAP gate.

    cmat TOF {cmat::Identity(8, 8)}

           Toffoli gate.
```

Private Member Functions

Fredkin gate.

• Gates ()

Initializes the gates.

cmat FRED {cmat::Identity(8, 8)}

∼Gates ()=default

Default destructor.

Friends

class internal::Singleton < const Gates >

Additional Inherited Members

7.15.1 Detailed Description

const Singleton class that implements most commonly used gates

7.15.2 Constructor & Destructor Documentation

```
7.15.2.1 Gates()

qpp::Gates::Gates ( ) [inline], [private]

Initializes the gates.

7.15.2.2 ~Gates()

qpp::Gates::~Gates ( ) [private], [default]
```

7.15.3 Member Function Documentation

7.15.3.1 CTRL()

Default destructor.

Generates the multi-partite multiple-controlled-A gate in matrix form.

See also

```
qpp::applyCTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
n	Total number of subsystems
d	Subsystem dimensions

Returns

CTRL-A gate, as a matrix over the same scalar field as A

7.15.3.2 expandout() [1/3]

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

Α	Eigen expression
pos	Position
dims	Dimensions of the multi-partite system

Returns

Tensor product $I \otimes \cdots \otimes I \otimes A \otimes I \otimes \cdots \otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.15.3.3 expandout() [2/3]

Expands out.

See also

```
qpp::kron()
```

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Note

The std::initializer_list overload exists because otherwise, in the degenerate case when *dims* has only one element, the one element list is implicitly converted to the element's underlying type, i.e. qpp::idx, which has the net effect of picking the wrong (non-vector) qpp::expandout() overload

Parameters

Α	Eigen expression
pos	Position
dims	Dimensions of the multi-partite system

Returns

Tensor product $I \otimes \cdots \otimes I \otimes A \otimes I \otimes \cdots \otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.15.3.4 expandout() [3/3]

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

Α	Eigen expression
pos	Position
n	Number of subsystems
d	Subsystem dimensions

Returns

Tensor product $I\otimes\cdots\otimes I\otimes A\otimes I\otimes\cdots\otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.15.3.5 Fd()

```
cmat qpp::Gates::Fd (
    idx D = 2 ) const [inline]
```

Quantum Fourier transform gate for qudits.

Note

```
Defined as F = \sum_{j,k=0}^{D-1} \exp(2\pi \mathrm{i} jk/D) |j\rangle\langle k|
```

Parameters

D Dimension of the Hilbert space

Returns

Fourier transform gate for qudits

7.15.3.6 get_name()

Get the name of the most common qubit gates.

Note

Assumes that the gate U is represented by a square matrix. If not, returns the empty string

Parameters

U | Complex matrix representing the quantum gate

Returns

The name of the gate (if any), otherwise the empty string

7.15.3.7 ld()

```
template<typename Derived = Eigen::MatrixXcd>
Derived qpp::Gates::Id (
    idx D = 2 ) const [inline]
```

Identity gate.

Note

Can change the return type from complex matrix (default) by explicitly specifying the template parameter

Parameters

D Dimension of the Hilbert space

Returns

Identity gate on a Hilbert space of dimension D

7.15.3.8 MODMUL()

```
cmat qpp::Gates::MODMUL (
          idx a,
          idx N,
          idx n ) const [inline]
```

Modular multiplication gate for qubits Implements $|x\rangle \longrightarrow |ax \bmod N\rangle$.

Note

For the gate to be unitary, *a* and *N* should be co-prime. The function does not check co-primality in release versions!

The number of qubits required to implement the gate should satisfy $n \geq \lceil \log_2(N) \rceil$

Parameters

а	Positive integer less than N
N	Positive integer
n	Number of qubits required for implementing the gate

Returns

Modular multiplication gate

7.15.3.9 Rn()

Qubit rotation of *theta* about the 3-dimensional real (unit) vector *n*.

Parameters

theta	Rotation angle
n	3-dimensional real (unit) vector

Returns

Rotation gate

7.15.3.10 RX()

Qubit rotation of theta about the X axis.

Parameters

theta	Rotation angle

Returns

Rotation gate

7.15.3.11 RY()

Qubit rotation of theta about the Y axis.

Parameters

theta	Rotation angle

Returns

Rotation gate

7.15.3.12 RZ()

Qubit rotation of theta about the Z axis.

Parameters

theta	Rotation angle
-------	----------------

Returns

Rotation gate

7.15.3.13 SWAPd()

```
cmat qpp::Gates::SWAPd (
    idx D = 2 ) const [inline]
```

SWAP gate for qudits.

Parameters

D Dimension of the Hilbert space

Returns

SWAP gate for qudits

7.15.3.14 Xd()

```
cmat qpp::Gates::Xd (
        idx D = 2 ) const [inline]
```

Generalized X gate for qudits.

Note

```
Defined as X=\sum_{j=0}^{D-1}|j\oplus 1\rangle\langle j|, i.e. raising operator X|j\rangle=|j\oplus 1\rangle
```

Parameters

D Dimension of the Hilbert space

Returns

Generalized X gate for qudits

7.15.3.15 Zd()

```
cmat qpp::Gates::Zd (
    idx D = 2 ) const [inline]
```

Generalized Z gate for qudits.

Note

Defined as
$$Z = \sum_{j=0}^{D-1} \exp(2\pi \mathrm{i} j/D) |j\rangle\langle j|$$

Parameters

D Dimension of the Hilbert space

Returns

Generalized Z gate for qudits

7.15.4 Friends And Related Function Documentation

7.15.4.1 internal::Singleton < const Gates >

```
friend class internal::Singleton< const Gates > [friend]
```

7.15.5 Member Data Documentation

7.15.5.1 CNOT

```
cmat qpp::Gates::CNOT {cmat::Identity(4, 4)}
```

Controlled-NOT control target gate.

```
7.15.5.2 CNOTba
cmat qpp::Gates::CNOTba {cmat::Zero(4, 4)}
Controlled-NOT target->control gate.
7.15.5.3 CZ
cmat qpp::Gates::CZ {cmat::Identity(4, 4)}
Controlled-Phase gate.
7.15.5.4 FRED
cmat qpp::Gates::FRED {cmat::Identity(8, 8)}
Fredkin gate.
7.15.5.5 H
cmat qpp::Gates::H {cmat::Zero(2, 2)}
Hadamard gate.
7.15.5.6 ld2
cmat qpp::Gates::Id2 {cmat::Identity(2, 2)}
Identity gate.
```

7.15.5.7 S

S gate.

cmat qpp::Gates::S {cmat::Zero(2, 2)}

```
Generated by Doxygen
```

```
7.15.5.8 SWAP
cmat qpp::Gates::SWAP {cmat::Identity(4, 4)}
SWAP gate.
7.15.5.9 T
cmat qpp::Gates::T {cmat::Zero(2, 2)}
T gate.
7.15.5.10 TOF
cmat qpp::Gates::TOF {cmat::Identity(8, 8)}
Toffoli gate.
7.15.5.11 X
cmat qpp::Gates::X {cmat::Zero(2, 2)}
Pauli Sigma-X gate.
7.15.5.12 Y
cmat qpp::Gates::Y {cmat::Zero(2, 2)}
Pauli Sigma-Y gate.
7.15.5.13 Z
cmat qpp::Gates::Z {cmat::Zero(2, 2)}
```

· classes/gates.h

The documentation for this class was generated from the following file:


Pauli Sigma-Z gate.

7.16 qpp::QCircuit::GateStep Struct Reference

One step consisting only of gates/operators in the circuit.

#include <classes/circuits/circuits.h>

Collaboration diagram for qpp::QCircuit::GateStep:



Public Member Functions

• GateStep ()=default

Default constructor.

GateStep (GateType gate_type, std::size_t gate_hash, const std::vector < idx > &ctrl, const std::vector < idx > &trl, const std::vector < idx > &target, std::string name={})

Constructs a gate step instance.

Public Attributes

GateType gate_type_ = GateType::NONE

gate type

std::size_t gate_hash_

gate hash

std::vector< idx > ctrl

control

std::vector< idx > target_

target where the gate is applied

• std::string name_

custom name of the step

7.16.1 Detailed Description

One step consisting only of gates/operators in the circuit.

7.16.2 Constructor & Destructor Documentation

```
7.16.2.1 GateStep() [1/2]

qpp::QCircuit::GateStep::GateStep ( ) [default]
```

Default constructor.

7.16.2.2 GateStep() [2/2]

```
qpp::QCircuit::GateStep::GateStep (
    GateType gate_type,
    std::size_t gate_hash,
    const std::vector< idx > & ctrl,
    const std::vector< idx > & target,
    std::string name = {} ) [inline], [explicit]
```

Constructs a gate step instance.

Parameters

gate_type	Gate type
gate_hash	Hash of the quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes
name	Optional gate name

7.16.3 Member Data Documentation

```
7.16.3.1 ctrl_
std::vector<idx> qpp::QCircuit::GateStep::ctrl_
control
```

```
7.16.3.2 gate_hash_
std::size_t qpp::QCircuit::GateStep::gate_hash_
gate hash
7.16.3.3 gate_type_
GateType qpp::QCircuit::GateStep::gate_type_ = GateType::NONE
gate type
7.16.3.4 name_
std::string qpp::QCircuit::GateStep::name_
custom name of the step
7.16.3.5 target_
std::vector<idx> qpp::QCircuit::GateStep::target_
target where the gate is applied
The documentation for this struct was generated from the following file:
    · classes/circuits/circuits.h
       qpp::internal::HashEigen Class Reference
7.17
```

Functor for hashing Eigen expressions.

```
#include <functions.h>
```

Public Member Functions

template < typename Derived >
 std::size_t operator() (const Eigen::MatrixBase < Derived > &A) const

7.17.1 Detailed Description

Functor for hashing Eigen expressions.

7.17.2 Member Function Documentation

7.17.2.1 operator()()

The documentation for this class was generated from the following file:


· functions.h

7.18 qpp::IDisplay Class Reference

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

```
#include <classes/idisplay.h>
```

Inheritance diagram for qpp::IDisplay:



Public Member Functions

virtual ~IDisplay ()=default
 Default virtual destructor.

Private Member Functions

virtual std::ostream & display (std::ostream &os) const =0
 Must be overridden by all derived classes.

Friends

std::ostream & operator<< (std::ostream &os, const IDisplay &rhs)
 Overloads the extraction operator.

7.18.1 Detailed Description

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

This class defines friend std::ostream& operator<<(std::ostream& os, const qpp::IDisplay& rhs). The latter delegates the work to the pure private virtual function qpp::IDisplay::display() which has to be overridden by all derived classes.

7.18.2 Constructor & Destructor Documentation

```
7.18.2.1 ~IDisplay()

virtual qpp::IDisplay::~IDisplay ( ) [virtual], [default]

Default virtual destructor.
```

7.18.3 Member Function Documentation

```
7.18.3.1 display()
```

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implemented in qpp::QCircuit, qpp::QEngine, qpp::QCircuit::iterator::value_type_, qpp::Dynamic_bitset, qpp::internal::IOManipEigen, qpp::Timer< T, CLOCK_T >, qpp::internal::IOManipPointer< PointerType >, and qpp::internal::IOManipRange< InputIterator >.

7.18.4 Friends And Related Function Documentation

7.18.4.1 operator <<

Overloads the extraction operator.

Delegates the work to the virtual function qpp::IDisplay::display()

The documentation for this class was generated from the following file:


· classes/idisplay.h

7.19 qpp::IJSON Class Reference

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

```
#include <classes/idisplay.h>
```

Inheritance diagram for qpp::IJSON:



Public Member Functions

virtual ∼IJSON ()=default

Default virtual destructor.

virtual std::string to_JSON (bool enclosed_in_curly_brackets=true) const =0
 JSON representation of the derived instance, must be overridden by all derived classes.

7.19.1 Detailed Description

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

7.19.2 Constructor & Destructor Documentation

```
7.19.2.1 \simIJSON() virtual qpp::IJSON::\simIJSON ( ) [virtual], [default]
```

Default virtual destructor.

7.19.3 Member Function Documentation

JSON representation of the derived instance, must be overridden by all derived classes.

Parameters

Implemented in qpp::QCircuit, and qpp::QEngine.

The documentation for this class was generated from the following file:


· classes/idisplay.h

7.20 qpp::Init Class Reference


const Singleton class that performs additional initializations/cleanups

```
#include <classes/init.h>
```

Inheritance diagram for qpp::Init:



Collaboration diagram for qpp::Init:



Private Member Functions

- Init ()
 - Additional initializations.
- ∼Init ()

Cleanups.

Friends

class internal::Singleton < const Init >

Additional Inherited Members

7.20.1 Detailed Description

const Singleton class that performs additional initializations/cleanups

7 20 2	Constructor	& Destructor	Documentation
1.ZU.Z	CONSTRUCTOR	a nesilucioi	Documentation

```
7.20.2.1 Init()

qpp::Init::Init ( ) [inline], [private]
```

Additional initializations.

```
7.20.2.2 ~ Init()

qpp::Init::~Init ( ) [inline], [private]
```

Cleanups.

7.20.3 Friends And Related Function Documentation

```
7.20.3.1 internal::Singleton < const Init >
```

```
friend class internal::Singleton< const Init > [friend]
```

The documentation for this class was generated from the following file:


• classes/init.h

7.21 qpp::exception::InvalidIterator Class Reference


Invalid iterator.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::InvalidIterator:



Collaboration diagram for qpp::exception::InvalidIterator:



Public Member Functions

- std::string description () const override
 - Exception description.
- Exception (const std::string &where)

Constructs an exception.

7.21.1 Detailed Description

Invalid iterator.

7.21.2 Member Function Documentation

7.21.2.1 description()

```
std::string qpp::exception::InvalidIterator::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.21.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--


The documentation for this class was generated from the following file:

• classes/exception.h


7.22 qpp::internal::IOManipEigen Class Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipEigen:



Collaboration diagram for qpp::internal::IOManipEigen:



Public Member Functions

- template<typename Derived > IOManipEigen (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
- IOManipEigen (const cplx z, double chop=qpp::chop)

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- cmat A
- double chop_

7.22.1 Constructor & Destructor Documentation

7.22.2 Member Function Documentation

```
7.22.2.1 display()
```

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.22.3 Member Data Documentation

7.22.3.1 A_

```
cmat qpp::internal::IOManipEigen::A_ [private]
```

7.22.3.2 chop_

double qpp::internal::IOManipEigen::chop_ [private]


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


7.23 qpp::internal::IOManipPointer< PointerType > Class Template Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipPointer< PointerType >:



Collaboration diagram for qpp::internal::IOManipPointer< PointerType >:



Public Member Functions

- IOManipPointer (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)
- IOManipPointer (const IOManipPointer &)=default
- IOManipPointer & operator= (const IOManipPointer &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- const PointerType * p_
- idx N
- std::string separator_
- std::string start
- std::string end
- · double chop_

7.23.1 Constructor & Destructor Documentation

```
7.23.1.1 IOManipPointer() [1/2]
```

7.23.1.2 **IOManipPointer()** [2/2]

7.23.2 Member Function Documentation

7.23.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.23.2.2 operator=()

7.23.3 Member Data Documentation

```
7.23.3.1 chop_
```

```
template<typename PointerType>
double qpp::internal::IOManipPointer< PointerType >::chop_ [private]
```

7.23.3.2 end_

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::end_ [private]
```

7.23.3.3 N_

```
template<typename PointerType>
idx qpp::internal::IOManipPointer< PointerType >::N_ [private]
```

7.23.3.4 p_

```
template<typename PointerType>
const PointerType* qpp::internal::IOManipPointer< PointerType >::p_ [private]
```

7.23.3.5 separator_

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::separator_ [private]
```

7.23.3.6 start_

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::start_ [private]
```


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


7.24 qpp::internal::IOManipRange < InputIterator > Class Template Reference

```
#include <internal/classes/iomanip.h>
```

Inheritance diagram for qpp::internal::IOManipRange< InputIterator >:



Collaboration diagram for qpp::internal::IOManipRange< InputIterator >:



Public Member Functions

- IOManipRange (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)
- IOManipRange (const IOManipRange &)=default
- IOManipRange & operator= (const IOManipRange &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- InputIterator first_
- InputIterator last_
- std::string separator_
- std::string start_
- std::string end_
- double chop_

7.24.1 Constructor & Destructor Documentation

7.24.1.1 | IOManipRange() [1/2]

7.24.1.2 | IOManipRange() [2/2]

7.24.2 Member Function Documentation

7.24.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.24.2.2 operator=()

7.24.3 Member Data Documentation

```
7.24.3.1 chop_
template<typename InputIterator>
double qpp::internal::IOManipRange< InputIterator >::chop_ [private]
7.24.3.2 end
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::end_ [private]
7.24.3.3 first_
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::first_ [private]
7.24.3.4 last
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::last_ [private]
7.24.3.5 separator_
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::separator_ [private]
7.24.3.6 start
template<typename InputIterator>
```

The documentation for this class was generated from the following file:

std::string qpp::internal::IOManipRange< InputIterator >::start_ [private]


• internal/classes/iomanip.h

7.25 qpp::is_complex< T > Struct Template Reference


Checks whether the type is a complex type.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_complex< T >:



Collaboration diagram for qpp::is_complex< T >:



7.25.1 Detailed Description

template < typename T > struct qpp::is_complex < T >

Checks whether the type is a complex type.

Provides the constant member *value* which is equal to *true*, if the type is a complex type, i.e. *std::complex<T>*

The documentation for this struct was generated from the following file:


traits.h

7.26 qpp::is_complex < std::complex < T > > Struct Template Reference


Checks whether the type is a complex number type, specialization for complex types.

#include <traits.h>

Inheritance diagram for qpp::is_complex < std::complex < T > :



Collaboration diagram for qpp::is_complex< std::complex< T >>:



7.26.1 Detailed Description

 $\label{template} \begin{tabular}{ll} template < typename T > \\ struct qpp::is_complex < std::complex < T > > \\ \end{tabular}$

Checks whether the type is a complex number type, specialization for complex types.

The documentation for this struct was generated from the following file:


· traits.h

7.27 qpp::is_iterable < T, typename > Struct Template Reference


Checks whether T is compatible with an STL-like iterable container.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_iterable < T, typename >:



Collaboration diagram for qpp::is_iterable < T, typename >:



7.27.1 Detailed Description

template<typename T, typename = void> struct qpp::is_iterable< T, typename >

Checks whether T is compatible with an STL-like iterable container.

Provides the constant member *value* which is equal to *true*, if *T* is compatible with an iterable container, i.e. provides at least *begin()* and *end()* member functions and allows de-referencing. Otherwise, *value* is equal to *false*.

The documentation for this struct was generated from the following file:


traits.h

7.28 qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().begin())) > Struct Template Reference


Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(*(std::declval < T >().begin())) > :



Collaboration diagram for qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std:: \leftarrow :declval< T >().end()), decltype(*(std::declval< T >().begin()))>>:



7.28.1 Detailed Description

 $template < typename \ T > \\ struct \ qpp::is_iterable < T, \ to_void < \ decltype(std::declval < T > ().begin()), \ decltype(std::declval < T > ().end()), \ decltype(*(std \leftarrow ::declval < T > ().begin())) > \\ \end{cases}$

Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

The documentation for this struct was generated from the following file:

· traits.h

7.29 qpp::is_matrix_expression < Derived > Struct Template Reference


Checks whether the type is an Eigen matrix expression.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_matrix_expression< Derived >:



Collaboration diagram for qpp::is_matrix_expression< Derived >:



7.29.1 Detailed Description

template<typename Derived>
struct qpp::is_matrix_expression< Derived >

Checks whether the type is an Eigen matrix expression.

Provides the constant member *value* which is equal to *true*, if the type is an Eigen matrix expression of type *Eigen ∷MatrixBase Oerived >*. Otherwise, *value* is equal to *false*.

The documentation for this struct was generated from the following file:


· traits.h

7.30 qpp::QCircuit::iterator Class Reference

Quantum circuit bound-checking (safe) iterator.

#include <classes/circuits/circuits.h>

Collaboration diagram for qpp::QCircuit::iterator:



Classes

· class value_type_

Value type class for qpp::QCircuit::iterator.

Public Types

• using difference_type = long long

iterator trait

• using value_type = value_type_

iterator trait

using pointer = const value_type *

iterator trait

• using reference = const value_type &

iterator trait

using iterator_category = std::forward_iterator_tag

iterator trait

Public Member Functions

• iterator ()=default

Default constructor.

• iterator (const iterator &)=default

Default copy constructor.

• iterator & operator= (const iterator &)=default

Default copy assignment operator.

iterator & operator++ ()

Prefix increment operator.

iterator operator++ (int)

Postfix increment operator.

```
    bool operator== (const iterator &rhs) const
Equality operator.
```

• bool operator!= (iterator rhs) const

Inequality operator.

• const value_type_ & operator* () const

Safe de-referencing operator.

void set_begin_ (const QCircuit *qc)

Sets the iterator to std::begin(this)

void set_end_ (const QCircuit *qc)

Sets the iterator to std::begin(this)

Private Attributes

```
const QCircuit * qc_ {nullptr}
```

< non-owning pointer to the parent const quantum circuit

value_type_ elem_ {nullptr}

7.30.1 Detailed Description

Quantum circuit bound-checking (safe) iterator.

Note

The iterator is a const_iterator by default

7.30.2 Member Typedef Documentation

```
7.30.2.1 difference_type
```

```
using qpp::QCircuit::iterator::difference_type = long long
```

iterator trait

7.30.2.2 iterator_category

```
using qpp::QCircuit::iterator::iterator_category = std::forward_iterator_tag
```

iterator trait

```
7.30.2.3 pointer

using qpp::QCircuit::iterator::pointer = const value_type*
iterator trait

7.30.2.4 reference

using qpp::QCircuit::iterator::reference = const value_type&
iterator trait

7.30.2.5 value_type

using qpp::QCircuit::iterator::value_type = value_type_
iterator trait
```

7.30.3 Constructor & Destructor Documentation

7.30.4 Member Function Documentation

Default copy constructor.

Parameters

rhs Iterator against which the inequality is being tested

Returns

True if the iterators are not equal (bit by bit), false otherwise

```
7.30.4.2 operator*()
```

```
const value_type_& qpp::QCircuit::iterator::operator* ( ) const [inline]
```

Safe de-referencing operator.

Returns

Constant reference to the iterator element

```
7.30.4.3 operator++() [1/2]
```

```
iterator& qpp::QCircuit::iterator::operator++ ( ) [inline]
```

Prefix increment operator.

Returns

Reference to the current instance

```
7.30.4.4 operator++() [2/2]
```

Postfix increment operator.

Returns

Copy of the current instance before the increment

```
7.30.4.5 operator=()
```

Default copy assignment operator.

Returns

Reference to the current instance

```
7.30.4.6 operator==()
```

Equality operator.

Parameters

rhs | Iterator against which the equality is being tested

Returns

True if the iterators are equal, false otherwise

```
7.30.4.7 set_begin_()
```

Sets the iterator to std::begin(this)

Parameters

qc | Pointer to constant quantum circuit

```
7.30.4.8 set_end_()
```

Sets the iterator to std::begin(this)

Parameters

qc Pointer to constant quantum circuit

7.30.5 Member Data Documentation

```
7.30.5.1 elem_
value_type_ qpp::QCircuit::iterator::elem_ {nullptr} [private]

7.30.5.2 qc_
const QCircuit* qpp::QCircuit::iterator::qc_ {nullptr} [private]
< non-owning pointer to the parent const quantum circuit</pre>
```

The documentation for this class was generated from the following file:

• classes/circuits/circuits.h

7.31 qpp::make_void < Ts > Struct Template Reference

Helper for qpp::to_void<> alias template.

```
#include <traits.h>
```

Public Types

• typedef void type

7.31.1 Detailed Description

```
template<typename... Ts>
struct qpp::make_void< Ts>
```

Helper for qpp::to_void<>> alias template.

See also

qpp::to_void<>

7.31.2 Member Typedef Documentation

7.31.2.1 type

```
template<typename... Ts>
typedef void qpp::make_void< Ts >::type
```

The documentation for this struct was generated from the following file:


· traits.h

7.32 qpp::exception::MatrixMismatchSubsys Class Reference


Matrix mismatch subsystems exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::MatrixMismatchSubsys:



Collaboration diagram for qpp::exception::MatrixMismatchSubsys:



Public Member Functions

- std::string description () const override
 - Exception description.
- Exception (const std::string &where)

Constructs an exception.

7.32.1 Detailed Description

Matrix mismatch subsystems exception.

Matrix size mismatch subsystem sizes (e.g. in qpp::apply())

7.32.2 Member Function Documentation

7.32.2.1 description()

std::string qpp::exception::MatrixMismatchSubsys::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.32.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.33 qpp::exception::MatrixNotCvector Class Reference


Matrix is not a column vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotCvector:



Collaboration diagram for qpp::exception::MatrixNotCvector:



Public Member Functions

• std::string description () const override

Exception description.

Exception (const std::string &where)

Constructs an exception.

7.33.1 Detailed Description

Matrix is not a column vector exception.

Eigen::Matrix is not a column vector

7.33.2 Member Function Documentation

7.33.2.1 description()

```
std::string qpp::exception::MatrixNotCvector::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.33.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred	
-------	--	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.34 qpp::exception::MatrixNotRvector Class Reference


Matrix is not a row vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotRvector:



Collaboration diagram for qpp::exception::MatrixNotRvector:



Public Member Functions

• std::string description () const override

Exception description.

Exception (const std::string &where)

Constructs an exception.

7.34.1 Detailed Description

Matrix is not a row vector exception.

Eigen::Matrix is not a row vector

7.34.2 Member Function Documentation

7.34.2.1 description()

```
std::string qpp::exception::MatrixNotRvector::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.34.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred	
-------	--	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.35 qpp::exception::MatrixNotSquare Class Reference


Matrix is not square exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquare:



Collaboration diagram for qpp::exception::MatrixNotSquare:



Public Member Functions

• std::string description () const override

Exception description.

Exception (const std::string &where)

Constructs an exception.

7.35.1 Detailed Description

Matrix is not square exception.

Eigen::Matrix is not a square matrix

7.35.2 Member Function Documentation

7.35.2.1 description()

```
std::string qpp::exception::MatrixNotSquare::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.35.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred	
-------	--	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.36 qpp::exception::MatrixNotSquareNorCvector Class Reference


Matrix is not square nor column vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorCvector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorCvector:



Public Member Functions

• std::string description () const override

Exception description.

Exception (const std::string &where)

Constructs an exception.

7.36.1 Detailed Description

Matrix is not square nor column vector exception.

Eigen::Matrix is not a square matrix nor a column vector

7.36.2 Member Function Documentation

7.36.2.1 description()

std::string qpp::exception::MatrixNotSquareNorCvector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.36.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.37 qpp::exception::MatrixNotSquareNorRvector Class Reference


Matrix is not square nor row vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorRvector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorRvector:



Public Member Functions

• std::string description () const override

Exception description.

Exception (const std::string &where)

Constructs an exception.

7.37.1 Detailed Description

Matrix is not square nor row vector exception.

Eigen::Matrix is not a square matrix nor a row vector

7.37.2 Member Function Documentation

7.37.2.1 description()

std::string qpp::exception::MatrixNotSquareNorRvector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.37.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.38 qpp::exception::MatrixNotSquareNorVector Class Reference


Matrix is not square nor vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorVector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorVector:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.38.1 Detailed Description

Matrix is not square nor vector exception.

Eigen::Matrix is not a square matrix nor a row/column vector

7.38.2 Member Function Documentation

7.38.2.1 description()

std::string qpp::exception::MatrixNotSquareNorVector::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.38.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.39 qpp::exception::MatrixNotVector Class Reference


Matrix is not a vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotVector:



Collaboration diagram for qpp::exception::MatrixNotVector:



Public Member Functions

• std::string description () const override

Exception description.

Exception (const std::string &where)

Constructs an exception.

7.39.1 Detailed Description

Matrix is not a vector exception.

Eigen::Matrix is not a row or column vector

7.39.2 Member Function Documentation

7.39.2.1 description()

```
std::string qpp::exception::MatrixNotVector::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.39.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred	
-------	--	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.40 qpp::QCircuit::MeasureStep Struct Reference

One step consisting only of measurements in the circuit.

#include <classes/circuits/circuits.h>

Collaboration diagram for qpp::QCircuit::MeasureStep:



Public Member Functions

• MeasureStep ()=default

Default constructor.

MeasureStep (MeasureType measurement_type, const std::vector< std::size_t > &mats_hash, const std
 ::vector< idx > &target, idx c_reg, std::string name={})

Constructs a measurement step instance.

Public Attributes

MeasureType measurement_type_ = MeasureType::NONE

measurement type

- std::vector< std::size_t > mats_hash_
- std::vector< idx > target_

target where the measurement is applied

- idx c_reg_ {}
- std::string name_

custom name of the step

7.40.1 Detailed Description

One step consisting only of measurements in the circuit.

7.40.2 Constructor & Destructor Documentation

```
7.40.2.1 MeasureStep() [1/2]
```

```
qpp::QCircuit::MeasureStep::MeasureStep ( ) [default]
```

Default constructor.

7.40.2.2 MeasureStep() [2/2]

Constructs a measurement step instance.

Parameters

measurement_type	Measurement type
mats_hash	Vector of hashes of the measurement matrix/matrices
target	Target qudit indexes
c_reg	Classical register where the value of the measurement is stored
name	Optional gate name

7.40.3 Member Data Documentation

```
7.40.3.1 c_reg_
```

```
idx qpp::QCircuit::MeasureStep::c_reg_ {}
```

index of the classical register where the measurement result is being stored

```
7.40.3.2 mats_hash_
```

```
std::vector<std::size_t> qpp::QCircuit::MeasureStep::mats_hash_
```

hashes of measurement matrix/matrices

7.40.3.3 measurement_type_

```
MeasureType qpp::QCircuit::MeasureStep::measurement_type_ = MeasureType::NONE
```

measurement type

7.40.3.4 name_

std::string qpp::QCircuit::MeasureStep::name_

custom name of the step

7.40.3.5 target_

std::vector<idx> qpp::QCircuit::MeasureStep::target_

target where the measurement is applied

The documentation for this struct was generated from the following file:


· classes/circuits/circuits.h

7.41 qpp::exception::NoCodeword Class Reference


Codeword does not exist exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NoCodeword:



Collaboration diagram for qpp::exception::NoCodeword:



Public Member Functions

- std::string description () const override
 - Exception description.
- Exception (const std::string &where)

Constructs an exception.

7.41.1 Detailed Description

Codeword does not exist exception.

Codeword does not exist, thrown when calling qpp::Codes::codeword() with an invalid index

7.41.2 Member Function Documentation

7.41.2.1 description()

std::string qpp::exception::NoCodeword::description () const [inline], [override], [virtual]
Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.41.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.42 qpp::NoiseBase < T > Class Template Reference

Base class for all noise models, derive your particular noise model.

#include <classes/noise.h>

Collaboration diagram for qpp::NoiseBase< T >:



Public Types

• using noise_type = T

Public Member Functions

template<typename U = noise_type>
 NoiseBase (const std::vector< cmat > &Ks, typename std::enable_if< std::is_same< NoiseType::StateDependent,
 U >::value >::type *=nullptr)

Constructs a noise instance for StateDependent noise type.

• template<typename U = noise_type>

NoiseBase (const std::vector< cmat > &Ks, const std::vector< double > &probs, typename std::enable_if< std::is_same< NoiseType::StateIndependent, U >::value >::type *=nullptr)

Constructs a noise instance for StateIndependent noise type.

virtual ∼NoiseBase ()=default

Default virtual destructor.

idx get d () const noexcept

Qudit dimension.

std::vector < cmat > get_Ks () const

Vector of noise operators.

• std::vector< double > get_probs () const

Vector of probabilities corresponding to each noise operator.

idx get_last_idx () const

Index of the last occurring noise element.

double get_last_p () const

Probability of the last occurring noise element.

cmat get_last_K () const

Last occurring noise element.

virtual cmat operator() (const cmat &state) const

Function invocation operator, applies the underlying noise model on the state vector or density matrix state.

· virtual cmat operator() (const cmat &state, idx target) const

Function invocation operator, applies the underlying noise model on qudit target of the multi-partite state vector or density matrix state.

virtual cmat operator() (const cmat &state, const std::vector < idx > &target) const

Function invocation operator, applies the underlying correlated noise model on qudits specified by target of the multipartite state vector or density matrix state.

Protected Member Functions

void compute_probs_ (const cmat &state, const std::vector < idx > &target) const

Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

cmat compute_state_ (const cmat &state, const std::vector< idx > &target) const

Compute the resulting state after the noise was applied.

Protected Attributes

const std::vector< cmat > Ks_

Kraus operators.

std::vector< double > probs

probabilities

idx d_ {}

qudit dimension

idx i_ {}

index of the last occurring noise element

bool generated_ {false}

invoked, or if the noise is state-independent

7.42.1 Detailed Description

```
\label{eq:class} \begin{array}{l} \text{template}{<}\text{class T}{>} \\ \text{class qpp::NoiseBase}{<}\text{T}{>} \end{array}
```

Base class for all noise models, derive your particular noise model.

7.42.2 Member Typedef Documentation

7.42.2.1 noise_type

```
template<class T>
using qpp::NoiseBase< T >::noise_type = T
```

7.42.3 Constructor & Destructor Documentation

7.42.3.1 NoiseBase() [1/2]

Constructs a noise instance for StateDependent noise type.

Note

SFINAEd-out for StateIndependent noise

Parameters

Ks | Vector of noise (Kraus) operators that specify the noise

7.42.3.2 NoiseBase() [2/2]

```
template<class T>
template<typename U = noise_type>
```

Constructs a noise instance for StateIndependent noise type.

Note

SFINAEd-out for StateDependent noise

Parameters

Ks	Vector of noise (Kraus) operators that specify the noise
probs	Vector of probabilities corresponding to each Kraus operator

7.42.3.3 ∼NoiseBase()

```
template<class T>
virtual qpp::NoiseBase< T >::~NoiseBase () [virtual], [default]
```

Default virtual destructor.

7.42.4 Member Function Documentation

7.42.4.1 compute_probs_()

Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

Parameters

state	State vector or density matrix
target	Qudit indexes where the noise is applied

7.42.4.2 compute_state_()

Compute the resulting state after the noise was applied.

Parameters

state	State vector or density matrix
target	Qudit indexes where the noise is applied

Returns

Resulting state after the noise was applied

7.42.4.3 get_d()

```
template<class T>
idx qpp::NoiseBase< T >::get_d ( ) const [inline], [noexcept]
```

Qudit dimension.

Returns

Qudit dimension

7.42.4.4 get_Ks()

```
template<class T>
std::vector<cmat> qpp::NoiseBase< T >::get_Ks () const [inline]
```

Vector of noise operators.

Returns

Vector of noise operators

```
7.42.4.5 get_last_idx()
```

```
template<class T>
idx qpp::NoiseBase< T >::get_last_idx ( ) const [inline]
```

Index of the last occurring noise element.

Returns

Index of the last occurring noise element

7.42.4.6 get_last_K()

```
template<class T>
cmat qpp::NoiseBase< T >::get_last_K ( ) const [inline]
```

Last occurring noise element.

Returns

Last occurring noise element

7.42.4.7 get_last_p()

```
template<class T>
double qpp::NoiseBase< T >::get_last_p ( ) const [inline]
```

Probability of the last occurring noise element.

Returns

Probability of the last occurring noise element

7.42.4.8 get_probs()

```
template < class T >
std::vector < double > qpp::NoiseBase < T >::get_probs ( ) const [inline]
```

Vector of probabilities corresponding to each noise operator.

Returns

Probability vector

7.42.4.9 operator()() [1/3]

Function invocation operator, applies the underlying noise model on the state vector or density matrix state.

Parameters

State vector or density matrix	state
--------------------------------	-------

Returns

Resulting state vector or density matrix

Function invocation operator, applies the underlying noise model on qudit *target* of the multi-partite state vector or density matrix *state*.

Parameters

state	Multi-partite state vector or density matrix
target	Qudit index where the noise is applied

Returns

Resulting state vector or density matrix

Function invocation operator, applies the underlying correlated noise model on qudits specified by *target* of the multi-partite state vector or density matrix *state*.

const std::vector< idx > & target) const [inline], [virtual]

Parameters

state	Multi-partite state vector or density matrix
target	Qudit indexes where the correlated noise is applied

Returns

Resulting state vector or density matrix

7.42.5 Member Data Documentation

```
7.42.5.1 d_
template<class T>
idx qpp::NoiseBase< T >::d_ {} [mutable], [protected]
qudit dimension
7.42.5.2 generated
template<class T>
bool qpp::NoiseBase< T >::generated_ {false} [mutable], [protected]
invoked, or if the noise is state-independent
set to true after compute_state_() is
7.42.5.3 i_
template<class T>
idx qpp::NoiseBase< T >::i_ {} [mutable], [protected]
index of the last occurring noise element
```

```
7.42.5.4 Ks_
```

```
template<class T>
const std::vector<cmat> qpp::NoiseBase< T >::Ks_ [protected]
```

Kraus operators.

7.42.5.5 probs_

```
template < class T>
std::vector < double > qpp::NoiseBase < T >::probs_ [mutable], [protected]
```

probabilities

The documentation for this class was generated from the following file:

· classes/noise.h

7.43 qpp::NoiseType Class Reference

Contains template tags used to specify the noise type.

```
#include <classes/noise.h>
```

Classes

· class StateDependent

Template tag, used whenever the noise is state-dependent.

· class StateIndependent

Template tag, used whenever the noise is state-independent.

7.43.1 Detailed Description

Contains template tags used to specify the noise type.

The documentation for this class was generated from the following file:


• classes/noise.h

7.44 qpp::exception::NotBipartite Class Reference


Not bi-partite exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::NotBipartite:



Collaboration diagram for qpp::exception::NotBipartite:



Public Member Functions

- std::string description () const override Exception description.
- Exception (const std::string &where)

 Constructs an exception.

7.44.1 Detailed Description

Not bi-partite exception.

std::vector<idx> of dimensions has size different from 2

7.44.2 Member Function Documentation

7.44.2.1 description()

```
std::string qpp::exception::NotBipartite::description ( ) const [inline], [override], [virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.44.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.45 qpp::exception::NotImplemented Class Reference


Code not yet implemented.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception::NotImplemented:$



Collaboration diagram for qpp::exception::NotImplemented:



Public Member Functions

- std::string description () const override
 - Exception description.
- Exception (const std::string &where)

Constructs an exception.

7.45.1 Detailed Description

Code not yet implemented.

7.45.2 Member Function Documentation

7.45.2.1 description()

```
std::string qpp::exception::NotImplemented::description ( ) const [inline], [override], [virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.45.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
WIICIC	I TEXT LEDI ESCULUIU MUCIE THE EXCEDITOR OCCURRED

The documentation for this class was generated from the following file:


· classes/exception.h

7.46 qpp::exception::NotQubitCvector Class Reference


Column vector is not 2 x 1 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitCvector:



Collaboration diagram for qpp::exception::NotQubitCvector:



Public Member Functions

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.46.1 Detailed Description

Column vector is not 2 x 1 exception.

Eigen::Matrix is not 2 x 1

7.46.2 Member Function Documentation

7.46.2.1 description()

```
std::string qpp::exception::NotQubitCvector::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.46.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.47 qpp::exception::NotQubitMatrix Class Reference


Matrix is not 2 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitMatrix:



Collaboration diagram for qpp::exception::NotQubitMatrix:



Public Member Functions

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.47.1 Detailed Description

Matrix is not 2 x 2 exception.

Eigen::Matrix is not 2 x 2

7.47.2 Member Function Documentation

7.47.2.1 description()

std::string qpp::exception::NotQubitMatrix::description () const [inline], [override], [virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.47.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.48 qpp::exception::NotQubitRvector Class Reference


Row vector is not 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitRvector:



Collaboration diagram for qpp::exception::NotQubitRvector:



Public Member Functions

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.48.1 Detailed Description

Row vector is not 1 x 2 exception.

Eigen::Matrix is not 1 x 2

7.48.2 Member Function Documentation

7.48.2.1 description()

```
std::string qpp::exception::NotQubitRvector::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.48.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


· classes/exception.h

7.49 qpp::exception::NotQubitSubsys Class Reference


Subsystems are not qubits exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitSubsys:



Collaboration diagram for qpp::exception::NotQubitSubsys:



Public Member Functions

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.49.1 Detailed Description

Subsystems are not qubits exception.

Subsystems are not 2-dimensional (qubits)

7.49.2 Member Function Documentation

7.49.2.1 description()

std::string qpp::exception::NotQubitSubsys::description () const [inline], [override], [virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.49.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.50 qpp::exception::NotQubitVector Class Reference


Vector is not 2 x 1 nor 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitVector:



Collaboration diagram for qpp::exception::NotQubitVector:



Public Member Functions

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.50.1 Detailed Description

Vector is not 2 x 1 nor 1 x 2 exception.

Eigen::Matrix is not 2 x 1 nor 1 x 2

7.50.2 Member Function Documentation

7.50.2.1 description()

std::string qpp::exception::NotQubitVector::description () const [inline], [override], [virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.50.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

	where	Text representing where the exception occurred	1
--	-------	--	---

The documentation for this class was generated from the following file:


· classes/exception.h

7.51 qpp::exception::OutOfRange Class Reference


Argument out of range exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::OutOfRange:



Collaboration diagram for qpp::exception::OutOfRange:



Public Member Functions

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.51.1 Detailed Description

Argument out of range exception.

Argument out of range

7.51.2 Member Function Documentation

7.51.2.1 description()

```
std::string qpp::exception::OutOfRange::description ( ) const [inline], [override], [virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.51.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the	e exception occurred
-----------------------------------	----------------------

The documentation for this class was generated from the following file:


· classes/exception.h

7.52 qpp::exception::PermInvalid Class Reference


Invalid permutation exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermInvalid:



Collaboration diagram for qpp::exception::PermInvalid:



Public Member Functions

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.52.1 Detailed Description

Invalid permutation exception.

std::vector<idx> does note represent a valid permutation

7.52.2 Member Function Documentation

7.52.2.1 description()

```
std::string qpp::exception::PermInvalid::description ( ) const [inline], [override], [virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.52.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where Text representing where the	e exception occurred
-----------------------------------	----------------------

The documentation for this class was generated from the following file:


· classes/exception.h

7.53 qpp::exception::PermMismatchDims Class Reference


Permutation mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermMismatchDims:



Collaboration diagram for qpp::exception::PermMismatchDims:



Public Member Functions

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.53.1 Detailed Description

Permutation mismatch dimensions exception.

Size of the std::vector<idx> representing the permutation is different from the size of the std::vector<idx> of dimensions

7.53.2 Member Function Documentation

7.53.2.1 description()

```
std::string qpp::exception::PermMismatchDims::description ( ) const [inline], [override],
[virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.53.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

The documentation for this class was generated from the following file:


· classes/exception.h

7.54 qpp::QCircuit Class Reference


Quantum circuit class.

#include <classes/circuits/circuits.h>

Inheritance diagram for qpp::QCircuit:



Collaboration diagram for qpp::QCircuit:



Classes

• struct GateStep

One step consisting only of gates/operators in the circuit.

· class iterator

Quantum circuit bound-checking (safe) iterator.

struct MeasureStep

One step consisting only of measurements in the circuit.

Public Types

enum GateType {

GateType::NONE, GateType::SINGLE, GateType::TWO, GateType::THREE,

 ${\tt GateType::CUSTOM, GateType::FAN, GateType::SINGLE_CTRL_SINGLE_TARGET, GateType::SINGLE_CTRL_MULTIPLE_CTRL_SINGLE_CTRL_MULTIPLE_CTRL_SINGLE_CTRL_MULTIPLE_CTRL_SINGLE_CTRL_MULTIPLE_CTRL_SINGLE_CTRL_MULTIPLE_CTRL_SINGLE_CTRL_MULTIPLE_CTRL$

GateType::MULTIPLE CTRL SINGLE TARGET, GateType::MULTIPLE CTRL MULTIPLE TARGET,

GateType::CUSTOM CTRL, GateType::SINGLE cCTRL SINGLE TARGET,

GateType::SINGLE cCTRL MULTIPLE TARGET, GateType::MULTIPLE cCTRL SINGLE TARGET,

GateType::MULTIPLE_cCTRL_MULTIPLE_TARGET, GateType::CUSTOM_cCTRL }

Type of gate being executed in a gate step.

 enum MeasureType { MeasureType::NONE, MeasureType::MEASURE_Z, MeasureType::MEASURE_V, MeasureType::MEASURE V MANY }

Type of measurement being executed in a measurement step.

enum StepType { StepType::NONE, StepType::GATE, StepType::MEASUREMENT, StepType::NOP }

Types of each step in the quantum circuit.

using const iterator = iterator

both iterators are const_iterators

Public Member Functions

· iterator begin ()

Iterator to the first element.

· const iterator begin () const noexcept

Constant iterator to the first element.

const_iterator cbegin () const noexcept

Constant iterator to the first element.

· iterator end ()

Iterator to the next to the last element.

· const_iterator end () const noexcept

Constant iterator to the next to the last element.

· const_iterator cend () const noexcept

Constant iterator to the next to the last element.

QCircuit (idx nq, idx nc=0, idx d=2, std::string name={})

Constructs a quantum circuit.

virtual ~QCircuit ()=default

Default virtual destructor.

idx get_nq () const noexcept

Total number of qudits in the circuit.

• idx get_nc () const noexcept

Total number of classical dits in the circuit.

• idx get_d () const noexcept

Dimension of the comprising qudits.

• std::string get_name () const

Quantum circuit name.

• idx get measured (idx i) const

Check whether qudit i was already measured.

std::vector< idx > get_measured () const

Vector of already measured qudit indexes.

std::vector< idx > get non measured () const

Vector of non-measured qudit indexes.

idx get_gate_count (const std::string &name={}) const

Quantum circuit gate count.

idx get_gate_depth (const std::string &name={}) const

Quantum circuit gate depth.

idx get_measurement_count () const noexcept

Quantum circuit total measurement count.

idx get_measurement_count (const std::string &name) const

Quantum circuit measurement count.

idx get_step_count () const noexcept

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

idx get nop count () const

No-op count.

QCircuit & add qudit (idx i=-1)

Adds an additional qudit before qudit i (by default adds it at the end)

QCircuit & add dit (idx i=-1)

Adds an additional classical dit before dit i (by default adds it at the end)

QCircuit & gate (const cmat &U, idx i, std::string name={})

Applies the single qudit gate U on single qudit i.

QCircuit & gate (const cmat &U, idx i, idx j, std::string name={})

Applies the two qudit gate U on qudits i and j.

QCircuit & gate (const cmat &U, idx i, idx j, idx k, std::string name={})

Applies the three qudit gate U on qudits i, j and k.

QCircuit & gate fan (const cmat &U, const std::vector < idx > &target, std::string name={})

Applies the single qudit gate U on every qudit listed in target.

QCircuit & gate fan (const cmat &U, const std::initializer list< idx > &target, std::string name={})

Applies the single qudit gate U on every qudit listed in target.

QCircuit & gate_fan (const cmat &U, std::string name={})

Applies the single qudit gate U on every remaining non-measured qudit.

QCircuit & gate custom (const cmat &U, const std::vector < idx > &target, std::string name={})

Jointly applies the custom multiple qudit gate U on the qudit indexes specified by target.

QCircuit & QFT (const std::vector < idx > &target, bool swap=true)

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & QFT (bool swap=true)

Applies the quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

• QCircuit & TFQ (const std::vector < idx > &target, bool swap QPP UNUSED =true)

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & TFQ (const std::initializer_list< idx > &target, bool swap=true)

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & TFQ (bool swap=true)

Applies the inverse quantum Fourier transform (as a series of gates) on all of remaining non-measured gudits.

QCircuit & CTRL (const cmat &U, idx ctrl, idx target, std::string name={})

Applies the single qudit controlled gate U with control qudit ctrl and target qudit target.

• QCircuit & CTRL (const cmat &U, idx ctrl, const std::vector< idx > &target, std::string name={})

Applies the single qudit controlled gate U with control qudit ctrl on every qudit listed in target.

QCircuit & CTRL (const cmat &U, const std::vector< idx > &ctrl, idx target, std::string name={})

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on the target qudit target.

QCircuit & CTRL (const cmat &U, const std::vector< idx > &ctrl, const std::vector< idx > &target, std::string name={})

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on every qudit listed in target.

QCircuit & CTRL_custom (const cmat &U, const std::vector< idx > &ctrl, const std::vector< idx > &target, std::string name={})

Jointly applies the custom multiple-qudit controlled gate U with multiple control qudits listed in ctrl on the qudit indexes specified by target.

QCircuit & cCTRL (const cmat &U, idx ctrl dit, idx target, std::string name={})

Applies the single qubit controlled gate U with classical control dit ctrl and target qudit target.

QCircuit & cCTRL (const cmat &U, idx ctrl_dit, const std::vector< idx > &target, std::string name={})

Applies the single qudit controlled gate U with classical control dit ctrl on every qudit listed in target.

QCircuit & cCTRL (const cmat &U, const std::vector < idx > &ctrl_dits, idx target, std::string name={})

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on the target qudit target.

QCircuit & cCTRL (const cmat &U, const std::vector< idx > &ctrl_dits, const std::vector< idx > &target, std::string name={})

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on every qudit listed in target.

QCircuit & cCTRL_custom (const cmat &U, const std::vector< idx > &ctrl_dits, const std::vector< idx > &target, std::string name={})

Jointly applies the custom multiple-qudit controlled gate U with multiple classical control dits listed in ctrl on the qudit indexes specified by target.

QCircuit & measureZ (idx target, idx c_reg, std::string name={})

Measurement of single qudit in the computational basis (Z-basis)

QCircuit & measureV (const cmat &V, idx target, idx c_reg, std::string name={})

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

QCircuit & measureV (const cmat &V, const std::vector< idx > &target, idx c_reg, std::string name={})

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

· QCircuit & nop ()

No operation (no-op)

• std::string to_JSON (bool enclosed_in_curly_brackets=true) const override

qpp::IJOSN::to_JSON() override

Private Member Functions

void add_hash_ (const cmat &U, std::size_t hashU)

Adds matrix to the hash table.

const std::vector< MeasureStep > & get_measurements_ () const noexcept

Vector of qpp::QCircuit::MeasureStep.

const std::vector< GateStep > & get_gates_ () const noexcept

Vector of qpp::QCircuit::GateStep.

const std::unordered_map< std::size_t, cmat > & get_cmat_hash_tbl_ () const noexcept

Hash table with the matrices used in the circuit.

std::ostream & display (std::ostream &os) const override

qpp::IDisplay::display() override

Private Attributes

• idx ng

number of qudits

idx nc

number of classical "dits"

const idx d

qudit dimension

```
7.54 qpp::QCircuit Class Reference

    std::string name_

          optional circuit name

    std::vector< bool > measured

          keeps track of the measured gudits
    std::unordered_map< std::size_t, cmat > cmat_hash_tbl_ {}

    std::unordered_map< std::string, idx > count_{{}}

          gate counts

    std::unordered_map< std::string, idx > measurement_count_{}{}

          measurement counts
    std::vector< GateStep > gates_{}{}
          gates
    • std::vector< MeasureStep > measurements_{{}}
          measurements
    std::vector< StepType > step_types_{{}}
          type of each step
Friends

    class QEngine

    std::ostream & operator<< (std::ostream &os, const GateType &gate_type)</li>

          Extraction operator overload for qpp::QCircuit::GateType enum class.

    std::ostream & operator<< (std::ostream &os, const GateStep &gate step)</li>

          Extraction operator overload for qpp::QCircuit::GateStep class.

    std::ostream & operator<< (std::ostream &os, const MeasureType &measure_type)</li>
```

Extraction operator overload for qpp::QCircuit::MeasureType enum class.

Extraction operator overload for qpp::QCircuit::MeasureStep class.

• std::ostream & operator<< (std::ostream &os, const MeasureStep &measure_step)

7.54.1 Detailed Description

Quantum circuit class.

See also

qpp::QEngine

7.54.2 Member Typedef Documentation

```
7.54.2.1 const_iterator
using qpp::QCircuit::const_iterator = iterator
both iterators are const iterators
```

Member Enumeration Documentation 7.54.3

7.54.3.1 GateType

```
enum qpp::QCircuit::GateType [strong]
```

Type of gate being executed in a gate step.

Enumerator

NONE	represents no gate
SINGLE	unitary gate on a single qudit
TWO	unitary gate on 2 qudits
THREE	unitary gate on 3 qudits
CUSTOM	custom gate on multiple qudits
FAN	same unitary gate on multiple qudits
SINGLE_CTRL_SINGLE_TARGET	controlled 1 qudit unitary gate with one control and one target
SINGLE_CTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with one control and multiple targets
MULTIPLE_CTRL_SINGLE_TARGET	controlled 1 qudit unitary gate with multiple controls and single target
MULTIPLE_CTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with multiple controls and multiple targets
CUSTOM_CTRL	custom controlled gate with multiple controls and multiple targets
SINGLE_cCTRL_SINGLE_TARGET	controlled 1 qudit unitary gate with one classical control and one target
SINGLE_cCTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with one classical control and multiple targets
MULTIPLE_cCTRL_SINGLE_TARGET	controlled 1 qudit unitary gate with multiple classical controls and single target
MULTIPLE_cCTRL_MULTIPLE_TARGET	controlled 1 qudit unitary gate with multiple classical controls and multiple targets
CUSTOM_cCTRL	custom controlled gate with multiple classical controls and multiple targets

7.54.3.2 MeasureType

enum qpp::QCircuit::MeasureType [strong]

Type of measurement being executed in a measurement step.

Enumerator

NONE	represents no measurement
MEASURE_Z Z measurement of single qudit.	
MEASURE_V	measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix $\it V$
MEASURE_V_MANY measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix <i>V</i>	

7.54.3.3 StepType

enum qpp::QCircuit::StepType [strong]

Types of each step in the quantum circuit.

Enumerator

NONE	represents no step
GATE	quantum gate(s)
MEASUREMENT	measurement
NOP	no-op

7.54.4 Constructor & Destructor Documentation

7.54.4.1 QCircuit()

```
qpp::QCircuit::QCircuit (
    idx nq,
    idx nc = 0,
    idx d = 2,
    std::string name = {} ) [inline], [explicit]
```

Constructs a quantum circuit.

Note

The measurement results can only be stored in the classical dits of which number is specified by nc

Parameters

nq	Number of qbits	
nc	Number of classical dits (optional)	
d	Subsystem dimensions (optional, default is qubit, i.e. $d = 2$)	
name	Circuit name (optional)	

7.54.4.2 \sim QCircuit()

```
\label{eq:continuit} \mbox{virtual qpp::QCircuit::} \sim \mbox{QCircuit ( ) [virtual], [default]}
```

Default virtual destructor.

7.54.5 Member Function Documentation

7.54.5.1 add_dit()

```
QCircuit& qpp::QCircuit::add_dit ( idx \ i = -1 \ ) \quad [inline]
```

Adds an additional classical dit before dit *i* (by default adds it at the end)

Note

Classical dits with indexes greater than the newly inserted one have their indexes automatically incremented

Parameters

```
i Classical dit index
```

Returns

Reference to the current instance

7.54.5.2 add_hash_()

Adds matrix to the hash table.

Note

Throws if a hash collision is detected., i.e., if two different matrices have the same hash

Parameters

U	Complex matrix	
hashU	Hash value of U	

7.54.5.3 add_qudit()

Adds an additional qudit before qudit i (by default adds it at the end)

Note

Qudits with indexes greater than the newly inserted one have their indexes automatically incremented

Parameters

```
i Qudit index
```

Returns

Reference to the current instance

```
7.54.5.4 begin() [1/2]
iterator qpp::QCircuit::begin ( ) [inline]
```

Iterator to the first element.

Returns

Iterator to the first element

```
7.54.5.5 begin() [2/2]
const_iterator qpp::QCircuit::begin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

```
7.54.5.6 cbegin()
```

```
const_iterator qpp::QCircuit::cbegin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

Applies the single qubit controlled gate *U* with classical control dit *ctrl* and target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with classical control dit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate	
ctrl_dit	it Classical control dit index	
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the	
	classical control dits	
name	Optional gate name	

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate	
ctrl_dits	Classical control dits indexes	
target	Target qudit indexes; the gate <i>U</i> is applied on every one of them depending on the values of the classical control dits	
name	Optional gate name	

Returns

Reference to the current instance

7.54.5.11 cCTRL_custom()

Jointly applies the custom multiple-qudit controlled gate U with multiple classical control dits listed in ctrl on the qudit indexes specified by target.

Parameters

U	Multiple-qudit quantum gate	
ctrl_dits		
target	Target qudit indexes where the gate U is applied depending on the values of the classical control dits	
name	Optional gate name	

Returns

Reference to the current instance

7.54.5.12 cend()

```
const_iterator qpp::QCircuit::cend ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

Returns

Constant iterator to the next to the last element

idx target,

Applies the single qudit controlled gate *U* with control qudit *ctrl* and target qudit *target*.

std::string name = {}) [inline]

Parameters

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.14 CTRL() [2/4]
```

Applies the single qudit controlled gate *U* with control qudit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl Control qudit index	
target Target qudit indexes; the gate <i>U</i> is applied on every one of them depending on the values of the qudits	
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.15 CTRL() [3/4]
```

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.16 CTRL() [4/4]
```

```
QCircuit& qpp::QCircuit::CTRL (

const cmat & U,
```

```
const std::vector< idx > & ctrl,
const std::vector< idx > & target,
std::string name = {} ) [inline]
```

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate	
ctrl	Control qudit indexes	
target	Target qudit indexes; the gate <i>U</i> is applied on every one of them depending on the values of the contrapidits	
name	Optional gate name	

Returns

Reference to the current instance

7.54.5.17 CTRL_custom()

Jointly applies the custom multiple-qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the qudit indexes specified by *target*.

Parameters

U	Multiple-qudit quantum gate	
ctrl	Control qudit indexes	
target Target qudit indexes where the gate U is applied depending on the values of the		
name	Optional gate name	

Returns

Reference to the current instance

7.54.5.18 display()

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the quantum circuit

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.54.5.19 end() [1/2]
```

```
iterator qpp::QCircuit::end ( ) [inline]
```

Iterator to the next to the last element.

Returns

Iterator to the next to the last element

```
7.54.5.20 end() [2/2]
const_iterator qpp::QCircuit::end ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

Returns

Constant iterator to the next to the last element

Applies the single qudit gate *U* on single qudit *i*.

Parameters

U	Single qudit quantum gate
i	Qudit index
name Generated b	Optional gate name

Returns

Reference to the current instance

Applies the two qudit gate *U* on qudits *i* and *j*.

Parameters

U	Two qudit quantum gate	
i	Qudit index	
j	Qudit index	
name	Optional gate name	

Returns

Reference to the current instance

Applies the three qudit gate U on qudits i, j and k.

Parameters

U	Three qudit quantum gate	
i	Qudit index	
j	Qudit index	
k	Qudit index	
name	Optional gate name	

Returns

Reference to the current instance

7.54.5.24 gate_custom()

Jointly applies the custom multiple qudit gate *U* on the qudit indexes specified by *target*.

Parameters

U	Multiple qudit quantum gate
target	Subsystem indexes where the gate <i>U</i> is applied
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.25 gate_fan() [1/3]
```

Applies the single qudit gate *U* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
target	Target qudit indexes; the gate <i>U</i> is applied on every one of them
name	Optional gate name

Returns

Reference to the current instance

7.54.5.26 gate_fan() [2/3]

Applies the single qudit gate *U* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
target	Target qudit indexes; the gate U is applied on every one of them
name	Optional gate name

Returns

Reference to the current instance

```
7.54.5.27 gate_fan() [3/3]
```

Applies the single qudit gate *U* on every remaining non-measured qudit.

Parameters

U	Single qudit quantum gate	
name	Optional gate name	

Returns

Reference to the current instance

7.54.5.28 get_cmat_hash_tbl_()

```
const std::unordered_map<std::size_t, cmat>& qpp::QCircuit::get_cmat_hash_tbl_ ( ) const
[inline], [private], [noexcept]
```

Hash table with the matrices used in the circuit.

Returns

Hash table with the matrices used in the circuit

```
7.54.5.29 get_d()
```

```
idx qpp::QCircuit::get_d ( ) const [inline], [noexcept]
```

Dimension of the comprising qudits.

Returns

Qudit dimension

7.54.5.30 get_gate_count()

Quantum circuit gate count.

Note

If name is empty (default), returns the total gate count of the circuit

Parameters

name	Gate name (optional)
------	----------------------

Returns

Gate count

7.54.5.31 get_gate_depth()

Quantum circuit gate depth.

Note

If name is empty (default), returns the total gate depth of the circuit

Parameters

name	Gate name	(optional)

```
Returns
```

Gate depth

```
7.54.5.32 get_gates_()
const std::vector<GateStep>& qpp::QCircuit::get_gates_ ( ) const [inline], [private], [noexcept]
Vector of qpp::QCircuit::GateStep.
```

Returns

Vector of qpp::QCircuit::GateStep

```
7.54.5.33 get_measured() [1/2] idx qpp::QCircuit::get_measured ( idx i) const [inline]
```

Check whether qudit *i* was already measured.

Parameters

i Qudit index

Returns

True if qudit i was already measured, false othwewise

```
7.54.5.34 get_measured() [2/2]
std::vector<idx> qpp::QCircuit::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

```
7.54.5.35 get_measurement_count() [1/2]
idx qpp::QCircuit::get_measurement_count ( ) const [inline], [noexcept]
```

Quantum circuit total measurement count.

Returns

Total measurement count

Quantum circuit measurement count.

Parameters

name	Measurement name
------	------------------

Returns

Measurement count

```
7.54.5.37 get_measurements_()
```

```
const std::vector<MeasureStep>& qpp::QCircuit::get_measurements_ ( ) const [inline], [private],
[noexcept]
```

Vector of qpp::QCircuit::MeasureStep.

Returns

Vector of qpp::QCircuit::MeasureStep

```
7.54.5.38 get_name()
```

```
std::string qpp::QCircuit::get_name ( ) const [inline]
```

Quantum circuit name.

Returns

Quantum circuit name

```
7.54.5.39 get_nc()
idx qpp::QCircuit::get_nc ( ) const [inline], [noexcept]
Total number of classical dits in the circuit.
Returns
     Total number of classical dits
7.54.5.40 get_non_measured()
std::vector<idx> qpp::QCircuit::get_non_measured ( ) const [inline]
Vector of non-measured qudit indexes.
Returns
     Vector of non-measured qudit indexes
7.54.5.41 get_nop_count()
idx qpp::QCircuit::get_nop_count ( ) const [inline]
No-op count.
Returns
     No-op count
```

7.54.5.42 get_nq()

```
idx qpp::QCircuit::get_nq ( ) const [inline], [noexcept]
```

Total number of qudits in the circuit.

Returns

Total number of qudits

7.54.5.43 get_step_count()

```
idx qpp::QCircuit::get_step_count ( ) const [inline], [noexcept]
```

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

Returns

Total (gates + measurements) count

7.54.5.44 measureV() [1/2]

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V	
target	Qudit index	
c_reg	Classical register where the value of the measurement is stored	
name	Optional measurement name	

Returns

Reference to the current instance

7.54.5.45 measureV() [2/2]

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V	
target	Target qudit indexes that are jointly measured	
c_reg	Classical register where the value of the measurement is stored	
Genpenathenib	y ுஜர்ஞா al measurement name	

Returns

Reference to the current instance

7.54.5.46 measureZ()

Measurement of single qudit in the computational basis (Z-basis)

Parameters

target	Qudit index	
c_reg	Classical register where the value of the measurement is being stored	
name	Optional measurement name, default is "Measure Z"	

Returns

Reference to the current instance

```
7.54.5.47 nop()
```

```
QCircuit& qpp::QCircuit::nop ( ) [inline]
```

No operation (no-op)

Note

If the underlying step is executed on a noisy engine, then noise acts before it

Returns

Reference to the current instance

```
7.54.5.48 QFT() [1/3]
```

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

```
7.54.5.49 QFT() [2/3]
```

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the quantum Fourier transform is applied	
swap Swaps the qubits at the end (true by default)		

Returns

Reference to the current instance

```
7.54.5.50 QFT() [3/3]
```

Applies the quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

Parameters

swap	Swaps the qubits at the end (true by default)
------	---

Returns

Reference to the current instance

```
7.54.5.51 TFQ() [1/3]
```

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the inverse quantum Fourier transform is applied
swap Swaps the qubits at the end (true by default)	

Returns

Reference to the current instance

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the inverse quantum Fourier transform is applied	
swap	Swaps the qubits at the end (true by default)	

Returns

Reference to the current instance

Applies the inverse quantum Fourier transform (as a series of gates) on all of remaining non-measured qudits.

Parameters

swap	Swaps the qubits at the end (true by default)
------	---

Returns

Reference to the current instance

7.54.5.54 to_JSON()

qpp::IJOSN::to JSON() override

Displays the quantum circuit in JSON format

Parameters

nclosed_in_curly_brackets	If true, encloses the result in curly brackets
---------------------------	--

Returns

String containing the JSON representation of the quantum circuit

Implements qpp::IJSON.

7.54.6 Friends And Related Function Documentation

Extraction operator overload for qpp::QCircuit::GateType enum class.

Parameters

os	Output stream	
gate_type	qpp::QCircuit::GateType enum class	

Returns

Output stream

```
7.54.6.2 operator << [2/4]
```

Extraction operator overload for qpp::QCircuit::GateStep class.

Parameters

os	Output stream
gate_step	qpp::QCircuit::GateStep class

Returns

Output stream

```
7.54.6.3 operator << [3/4]
```

Extraction operator overload for qpp::QCircuit::MeasureType enum class.

Parameters

os		Output stream
measure_t	type	qpp::QCircuit::MeasureType enum class

Returns

Output stream

```
7.54.6.4 operator << [4/4]
```

```
std::ostream& operator<< (
          std::ostream & os,
          const MeasureStep & measure_step ) [friend]</pre>
```

Extraction operator overload for qpp::QCircuit::MeasureStep class.

Parameters

os	Output stream
measure step	qpp::QCircuit::MeasureStep enum class

```
Returns
```

Output stream

```
7.54.6.5 QEngine
friend class QEngine [friend]
7.54.7 Member Data Documentation
7.54.7.1 cmat_hash_tbl_
std::unordered_map<std::size_t, cmat> qpp::QCircuit::cmat_hash_tbl_ {} [private]
hash table with the matrices used in the circuit, with [Key = idx, Value = cmat]
7.54.7.2 count_
std::unordered_map<std::string, idx> qpp::QCircuit::count_ {} [private]
gate counts
7.54.7.3 d_
const idx qpp::QCircuit::d_ [private]
qudit dimension
7.54.7.4 gates_
std::vector<GateStep> qpp::QCircuit::gates_ {} [private]
```

gates

```
7.54.7.5 measured_
std::vector<bool> qpp::QCircuit::measured_ [private]
keeps track of the measured qudits
7.54.7.6 measurement_count_
std::unordered_map<std::string, idx> qpp::QCircuit::measurement_count_ {} [private]
measurement counts
7.54.7.7 measurements_
std::vector<MeasureStep> qpp::QCircuit::measurements_ {} [private]
measurements
7.54.7.8 name_
std::string qpp::QCircuit::name_ [private]
optional circuit name
7.54.7.9 nc
idx qpp::QCircuit::nc_ [private]
number of classical "dits"
7.54.7.10 nq_
idx qpp::QCircuit::nq_ [private]
number of qudits
```

7.54.7.11 step_types_

```
std::vector<StepType> qpp::QCircuit::step_types_ {} [private]
```

type of each step

The documentation for this class was generated from the following file:


· classes/circuits/circuits.h

7.55 qpp::QEngine Class Reference


Quantum circuit engine, executes qpp::QCircuit.

```
#include <classes/circuits/engines.h>
```

Inheritance diagram for qpp::QEngine:



 $Collaboration\ diagram\ for\ qpp:: QEngine:$



Public Member Functions

QEngine (const QCircuit &qc)

Constructs a quantum engine out of a quantum circuit.

QEngine (const QEngine &)=default

Default copy constructor.

• QEngine & operator= (const QEngine &)=default

Default copy assignment operator.

• QEngine (QCircuit &&)=delete

Disables rvalue QCircuit.

virtual ~QEngine ()=default

Default virtual destructor.

• ket get_psi () const

Underlying quantum state.

• std::vector< idx > get_dits () const

Vector with the values of the underlying classical dits.

• idx get_dit (idx i) const

Value of the classical dit at position i.

• std::vector< double > get_probs () const

Vector of underlying measurement outcome probabilities.

bool get_measured (idx i) const

Check whether qudit i was already measured.

std::vector< idx > get_measured () const

Vector of already measured qudit indexes.

std::vector< idx > get_non_measured () const

Vector of non-measured qudit indexes.

const QCircuit & get_circuit () const noexcept

Quantum circuit.

QEngine & set_dit (idx i, idx value)

Sets the classical dit at position i.

QEngine & set_psi (const ket &psi)

Sets the underlying quantum state to psi.

void reset ()

Resets the engine.

virtual void execute (const QCircuit::iterator::value type &elem)

Executes one step in the quantum circuit.

• void execute (const QCircuit::iterator &it)

Executes one step in the quantum circuit.

• void execute ()

Executes the entire quantum circuit.

• std::string to_JSON (bool enclosed_in_curly_brackets=true) const override

qpp::IJOSN::to_JSON() override

Protected Member Functions

• void set_measured_ (idx i)

Marks qudit i as measured then re-label accordingly the remaining non-measured qudits.

std::vector< idx > get_relative_pos_ (std::vector< idx > v)

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

Protected Attributes

```
    const QCircuit * qc_
        pointer to constant quantum circuit
    ket psi_
        state vector
    std::vector < idx > dits_
        classical dits
    std::vector < double > probs_
        measurement probabilities
    std::vector < idx > subsys_
```

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display() override*

7.55.1 Detailed Description

Quantum circuit engine, executes qpp::QCircuit.

See also

qpp::QCircuit

7.55.2 Constructor & Destructor Documentation

Constructs a quantum engine out of a quantum circuit.

Note

The quantum circuit must be an Ivalue

See also

```
qpp::QEngine(QCircuit&&)
```

Note

The initial underlying quantum state is set to $|0\rangle^{\otimes n}$

Parameters

```
qc Quantum circuit
```

Default copy constructor.

Disables rvalue QCircuit.

```
7.55.2.4 \sim QEngine()
```

```
\label{eq:condition} \mbox{virtual qpp::QEngine::} \sim \mbox{QEngine ( ) [virtual], [default]}
```

Default virtual destructor.

7.55.3 Member Function Documentation

```
7.55.3.1 display()
```

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the state of the engine

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

Executes one step in the quantum circuit.

Parameters

```
elem Step to be executed
```

Reimplemented in qpp::QNoisyEngine < NoiseModel >.

Executes one step in the quantum circuit.

Parameters

it Iterator to the step to be executed

```
7.55.3.4 execute() [3/3]
void qpp::QEngine::execute ( ) [inline]
```

Executes the entire quantum circuit.

```
7.55.3.5 get_circuit()
const QCircuit& qpp::QEngine::get_circuit ( ) const [inline], [noexcept]
```

Quantum circuit.

Returns

Underlying quantum circuit

7.55.3.6 get_dit()

```
idx qpp::QEngine::get_dit (
        idx i ) const [inline]
```

Value of the classical dit at position i.

Parameters

```
i Classical dit index
```

Returns

Value of the classical dit at position i

7.55.3.7 get_dits()

```
std::vector<idx> qpp::QEngine::get_dits ( ) const [inline]
```

Vector with the values of the underlying classical dits.

Returns

Vector of underlying classical dits

```
7.55.3.8 get_measured() [1/2]
```

```
bool qpp::QEngine::get_measured (
        idx i ) const [inline]
```

Check whether qudit *i* was already measured.

Parameters

i Qudit index

Returns

True if qudit *i* was already measured, false othwewise

```
7.55.3.9 get_measured() [2/2]
std::vector<idx> qpp::QEngine::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

```
7.55.3.10 get_non_measured()
```

```
std::vector<idx> qpp::QEngine::get_non_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

Returns

Vector of non-measured qudit indexes

```
7.55.3.11 get_probs()
```

```
std::vector<double> qpp::QEngine::get_probs ( ) const [inline]
```

Vector of underlying measurement outcome probabilities.

Those should be interpreted as conditional probabilities based on the temporal order of the measurements, i.e. if we measure qubit 0, then measure qubit 1, and finally qubit 2, the resulting vector of outcome probabilities probs[2] should be interpreted as the conditional probability of qubit 2 having the outcome it had given that qubit 1 and qubit 0 had their given outcomes, respectively. As an example, if we measure the qubit 0 followed by the qubit 1 of a maximally entangled state $(|00\rangle + |11\rangle)/\sqrt{2}$, then the vector of outcome probabilities will be [0.5, 1].

Note

The probability vector has the same length as the vector of classical dits. If the measurement result is stored at the index c_reg , then the outcome probability is automatically stored at the same index c_reg in the probability vector.

Returns

Vector of underlying measurement outcome probabilities

```
7.55.3.12 get_psi()
```

```
ket qpp::QEngine::get_psi ( ) const [inline]
```

Underlying quantum state.

Returns

Underlying quantum state

7.55.3.13 get_relative_pos_()

```
\label{eq:condition} $$ std::vector < idx > qpp::QEngine::get_relative_pos_ ( \\ std::vector < idx > v ) [inline], [protected] $$
```

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

Parameters



Returns

Vector of qudit indexes

7.55.3.14 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

7.55.3.15 reset()

```
void qpp::QEngine::reset ( ) [inline]
```

Resets the engine.

Re-initializes everything to zero and sets the initial state to $|0\rangle^{\otimes n}$

```
7.55.3.16 set_dit()
```

```
QEngine& qpp::QEngine::set_dit (
          idx i,
          idx value ) [inline]
```

Sets the classical dit at position i.

Parameters

i	Classical dit index
value	Classical dit value

Returns

Reference to the current instance

7.55.3.17 set_measured_()

```
void qpp::QEngine::set_measured_ (
          idx i ) [inline], [protected]
```

Marks qudit *i* as measured then re-label accordingly the remaining non-measured qudits.

Parameters

i Qudit index

7.55.3.18 set_psi()

Sets the underlying quantum state to psi.

Note

The order is lexicographical with respect to the remaining non-measured qudits

Parameters

psi State vector

Returns

Reference to the current instance

```
7.55.3.19 to_JSON()
```

qpp::IJOSN::to_JSON() override

Displays the state of the engine in JSON format

Parameters

enclosed_in_curly_brackets	If true, encloses the result in curly brackets
----------------------------	--

Returns

String containing the JSON representation of the state of the engine

Implements qpp::IJSON.

7.55.4 Member Data Documentation

```
7.55.4.1 dits_
std::vector<idx> qpp::QEngine::dits_ [protected]
classical dits
```

```
7.55.4.2 probs_
```

std::vector<double> qpp::QEngine::probs_ [protected]

measurement probabilities

```
7.55.4.3 psi_
ket qpp::QEngine::psi_ [protected]
```

state vector

7.55.4.4 qc_

```
const QCircuit* qpp::QEngine::qc_ [protected]
```

pointer to constant quantum circuit

7.55.4.5 subsys_

```
std::vector<idx> qpp::QEngine::subsys_ [protected]
```

keeps track of the measured subsystems, relabel them after measurements

The documentation for this class was generated from the following file:


· classes/circuits/engines.h

7.56 qpp::QNoisyEngine < NoiseModel > Class Template Reference


Noisy quantum circuit engine, executes qpp::QCircuit.

```
#include <classes/circuits/engines.h>
```

Inheritance diagram for qpp::QNoisyEngine < NoiseModel >:



Collaboration diagram for qpp::QNoisyEngine < NoiseModel >:



Public Member Functions

• QNoisyEngine (const QCircuit &qc, const NoiseModel &noise)

Constructs a noisy quantum engine out of a quantum circuit.

void execute (const QCircuit::iterator::value_type &elem) override

Executes one step in the quantum circuit.

• $std::vector < std::vector < idx >> get_noise_results$ () const

Vector of noise results obtained before every step in the circuit.

virtual void execute (const QCircuit::iterator::value type &elem)

Executes one step in the quantum circuit.

• void execute (const QCircuit::iterator &it)

Executes one step in the quantum circuit.

• void execute ()

Executes the entire quantum circuit.

Private Attributes

• const NoiseModel noise_

quantum noise model

std::vector< std::vector< idx >> noise results

noise results

Additional Inherited Members

7.56.1 Detailed Description

$$\label{local_total_constraints} \begin{split} \text{template} &< \text{typename NoiseModel} > \\ \text{class qpp::QNoisyEngine} &< \text{NoiseModel} > \end{split}$$

Noisy quantum circuit engine, executes qpp::QCircuit.

See also

qpp::QCircuit, qpp::NoiseBase

Assumes an uncorrelated noise model that is applied to each non-measured qubit before every step in the logical circuit

Template Parameters

NoiseModel Quantum noise model, should be derived from qpp::No	seBase
--	--------

7.56.2 Constructor & Destructor Documentation

7.56.2.1 QNoisyEngine()

Constructs a noisy quantum engine out of a quantum circuit.

Parameters

qc	Quantum circuit
noise	Quantum noise model

7.56.3 Member Function Documentation

```
7.56.3.1 execute() [1/4]

template<typename NoiseModel >
virtual void qpp::QEngine::execute [inline]
```

Executes one step in the quantum circuit.

Parameters

elem	Step to be executed
------	---------------------

```
7.56.3.2 execute() [2/4]
```

```
template<typename NoiseModel >
void qpp::QEngine::execute [inline]
```

Executes the entire quantum circuit.

```
7.56.3.3 execute() [3/4]
```

```
template<typename NoiseModel >
void qpp::QEngine::execute [inline]
```

Executes one step in the quantum circuit.

Parameters

```
it Iterator to the step to be executed
```

7.56.3.4 execute() [4/4]

Executes one step in the quantum circuit.

Parameters

```
elem Step to be executed
```

Reimplemented from qpp::QEngine.

7.56.3.5 get_noise_results()

```
template<typename NoiseModel >
std::vector<std::vector<idx> > qpp::QNoisyEngine< NoiseModel >::get_noise_results ( ) const
[inline]
```

Vector of noise results obtained before every step in the circuit.

The first vector contains the noise measurement results obtained before applying the first step in the circuit, and so on, ordered by non-measured qudits. That is, the first element in the vector corresponding to noise obtained before a given step in the circuit represents the noise result obtained on the first non-measured qudit etc.

Returns

Vector of noise results

7.56.4 Member Data Documentation

7.56.4.1 noise_

```
template<typename NoiseModel >
const NoiseModel qpp::QNoisyEngine< NoiseModel >::noise_ [private]
```

quantum noise model

7.56.4.2 noise_results_

```
template<typename NoiseModel >
std::vector<std::vector<idx> > qpp::QNoisyEngine< NoiseModel >::noise_results_ [private]
```

noise results

The documentation for this class was generated from the following file:


· classes/circuits/engines.h

7.57 qpp::QubitAmplitudeDampingNoise Class Reference


Qubit amplitude damping noise, as described in Nielsen and Chuang.

```
#include <classes/noise.h>
```

 $Inheritance\ diagram\ for\ qpp:: Qubit Amplitude Damping Noise:$



Collaboration diagram for qpp::QubitAmplitudeDampingNoise:



Public Member Functions

QubitAmplitudeDampingNoise (double gamma)
 Qubit amplitude damping noise constructor.

Additional Inherited Members

7.57.1 Detailed Description

Qubit amplitude damping noise, as described in Nielsen and Chuang.

7.57.2 Constructor & Destructor Documentation

7.57.2.1 QubitAmplitudeDampingNoise()

Qubit amplitude damping noise constructor.

Parameters

gamma	Amplitude damping coefficient

The documentation for this class was generated from the following file:


· classes/noise.h

7.58 qpp::QubitBitFlipNoise Class Reference


Qubit bit flip noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitBitFlipNoise:



Collaboration diagram for qpp::QubitBitFlipNoise:



Public Member Functions

QubitBitFlipNoise (double p)
 Qubit bit flip noise constructor.

Additional Inherited Members

7.58.1 Detailed Description

Qubit bit flip noise.

7.58.2 Constructor & Destructor Documentation

7.58.2.1 QubitBitFlipNoise()

Qubit bit flip noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.59 qpp::QubitBitPhaseFlipNoise Class Reference


Qubit bit-phase flip (dephasing) noise.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitBitPhaseFlipNoise:



Collaboration diagram for qpp::QubitBitPhaseFlipNoise:



Public Member Functions

QubitBitPhaseFlipNoise (double p)
 Qubit bit-phase flip noise constructor.

Additional Inherited Members

7.59.1 Detailed Description

Qubit bit-phase flip (dephasing) noise.

7.59.2 Constructor & Destructor Documentation

7.59.2.1 QubitBitPhaseFlipNoise()

```
\label{eq:qpp::QubitBitPhaseFlipNoise::QubitBitPhaseFlipNoise (} $$ double $p$ ) [inline], [explicit]
```

Qubit bit-phase flip noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.60 qpp::QubitDepolarizingNoise Class Reference


Qubit depolarizing noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitDepolarizingNoise:



Collaboration diagram for qpp::QubitDepolarizingNoise:



Public Member Functions

QubitDepolarizingNoise (double p)
 Qubit depolarizing noise constructor.

Additional Inherited Members

7.60.1 Detailed Description

Qubit depolarizing noise.

7.60.2 Constructor & Destructor Documentation

7.60.2.1 QubitDepolarizingNoise()

```
\label{eq:qpp::QubitDepolarizingNoise::QubitDepolarizingNoise (} \\ \text{double } p \text{ ) } \quad \text{[inline], [explicit]}
```

Qubit depolarizing noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


classes/noise.h

7.61 qpp::QubitPhaseDampingNoise Class Reference


Qubit phase damping noise, as described in Nielsen and Chuang.

```
#include <classes/noise.h>
```

 $Inheritance\ diagram\ for\ qpp:: Qubit Phase Damping Noise:$



Collaboration diagram for qpp::QubitPhaseDampingNoise:



Public Member Functions

QubitPhaseDampingNoise (double lambda)
 Qubit phase damping noise constructor.

Additional Inherited Members

7.61.1 Detailed Description

Qubit phase damping noise, as described in Nielsen and Chuang.

7.61.2 Constructor & Destructor Documentation

7.61.2.1 QubitPhaseDampingNoise()

```
\label{lem:qpp::QubitPhaseDampingNoise::QubitPhaseDampingNoise (} \\ \mbox{double } lambda \mbox{ ) [inline], [explicit]}
```

Qubit phase damping noise constructor.

Parameters

lambda	Phase damping coefficient

The documentation for this class was generated from the following file:


· classes/noise.h

7.62 qpp::QubitPhaseFlipNoise Class Reference


Qubit phase flip (dephasing) noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitPhaseFlipNoise:



Collaboration diagram for qpp::QubitPhaseFlipNoise:



Public Member Functions

QubitPhaseFlipNoise (double p)
 Qubit phase flip (dephasing) noise constructor.

Additional Inherited Members

7.62.1 Detailed Description

Qubit phase flip (dephasing) noise.

7.62.2 Constructor & Destructor Documentation

7.62.2.1 QubitPhaseFlipNoise()

Qubit phase flip (dephasing) noise constructor.

Parameters

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

7.63 qpp::exception::QuditAlreadyMeasured Class Reference


Qudit was already measured exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::QuditAlreadyMeasured:



Collaboration diagram for qpp::exception::QuditAlreadyMeasured:



Public Member Functions

- std::string description () const override
 - Exception description.
- Exception (const std::string &where)

Constructs an exception.

7.63.1 Detailed Description

Qudit was already measured exception.

The qudit was already measured and cannot be measured again

7.63.2 Member Function Documentation

7.63.2.1 description()

std::string qpp::exception::QuditAlreadyMeasured::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.63.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

The documentation for this class was generated from the following file:


· classes/exception.h

7.64 qpp::QuditDepolarizingNoise Class Reference


Qudit depolarizing noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QuditDepolarizingNoise:



Collaboration diagram for qpp::QuditDepolarizingNoise:



Public Member Functions

QuditDepolarizingNoise (double p, idx d)
 Qudit depolarizing noise constructor.

Private Member Functions

std::vector< cmat > fill_Ks_ (idx d) const

Fills the Kraus operator vector.

std::vector< double > fill_probs_ (double p, idx d) const
 Fills the probability vector.

Additional Inherited Members

7.64.1 Detailed Description

Qudit depolarizing noise.

7.64.2 Constructor & Destructor Documentation

7.64.2.1 QuditDepolarizingNoise()

```
qpp::QuditDepolarizingNoise::QuditDepolarizingNoise ( double p,  idx \ d \ ) \ \ [inline], \ [explicit]
```

Qudit depolarizing noise constructor.

Parameters

р	Noise probability
d	Qudit dimension

7.64.3 Member Function Documentation

```
7.64.3.1 fill_Ks_()
```

Fills the Kraus operator vector.

Parameters

```
d Qudit dimension
```

Returns

Vector of Kraus operators representing the depolarizing noise

```
7.64.3.2 fill_probs_()
```

Fills the probability vector.

Parameters

р	Probability
d	Qudit dimension

Returns

Probability vector

The documentation for this class was generated from the following file:


• classes/noise.h

7.65 qpp::RandomDevices Class Reference


Singleton class that manages the source of randomness in the library.

#include <classes/random_devices.h>

Inheritance diagram for qpp::RandomDevices:



Collaboration diagram for qpp::RandomDevices:



Public Member Functions

• std::mt19937 & get_prng ()

Returns a reference to the internal PRNG object.

• std::istream & load (std::istream &is)

Loads the state of the PRNG from an input stream.

• std::ostream & save (std::ostream &os) const

Saves the state of the PRNG to an output stream.

Private Member Functions

• RandomDevices ()

Initializes and seeds the random number generators.

∼RandomDevices ()=default

Default destructor.

Private Attributes

 std::random_device rd_ used to seed std::mt19937 prng_

std::mt19937 prng_

Mersenne twister random number generator.

Friends

class internal::Singleton < RandomDevices >

Additional Inherited Members

7.65.1 Detailed Description

Singleton class that manages the source of randomness in the library.

Consists of a wrapper around an std::mt19937 Mersenne twister random number generator engine and an std

∴ random_device engine. The latter is used to seed the Mersenne twister.

Warning

This class DOES NOT seed the standard C number generator used by Eigen::Matrix::Random(), since it is not thread safe. Do not use Eigen::Matrix::Random() or functions that depend on the C style random number engine, but use qpp::rand() instead!

7.65.2 Constructor & Destructor Documentation

7.65.2.1 RandomDevices()

```
qpp::RandomDevices::RandomDevices ( ) [inline], [private]
```

Initializes and seeds the random number generators.

7.65.2.2 ~RandomDevices()

```
\verb"qpp::RandomDevices::$\sim$RandomDevices ( ) [private], [default]
```

Default destructor.

7.65.3 Member Function Documentation

```
7.65.3.1 get_prng()
```

```
std::mt19937& qpp::RandomDevices::get_prng ( ) [inline]
```

Returns a reference to the internal PRNG object.

Returns

Reference to the internal PRNG object

7.65.3.2 load()

```
std::istream& qpp::RandomDevices::load (  \texttt{std::istream \& } is \ ) \quad [inline]
```

Loads the state of the PRNG from an input stream.

Parameters

```
is Input stream
```

Returns

The input stream

7.65.3.3 save()

Saves the state of the PRNG to an output stream.

Parameters

os Output stream

Returns

The output stream

7.65.4 Friends And Related Function Documentation

```
7.65.4.1 internal::Singleton < Random Devices >
```

```
friend class internal::Singleton< RandomDevices > [friend]
```

7.65.5 Member Data Documentation

```
7.65.5.1 prng_
```

```
std::mt19937 qpp::RandomDevices::prng_ [private]
```

Mersenne twister random number generator.

```
7.65.5.2 rd_
```

```
std::random_device qpp::RandomDevices::rd_ [private]
```

used to seed std::mt19937 prng_

The documentation for this class was generated from the following file:

• classes/random_devices.h

7.66 qpp::internal::Singleton < T > Class Template Reference

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

```
#include <internal/classes/singleton.h>
```

Static Public Member Functions

- static T & get_instance () noexcept(std::is_nothrow_constructible < T >::value)
- static T & get_thread_local_instance () noexcept(std::is_nothrow_constructible < T >::value)

Protected Member Functions

- Singleton () noexcept=default
- Singleton (const Singleton &)=delete
- Singleton & operator= (const Singleton &)=delete
- virtual ∼Singleton ()=default

7.66.1 Detailed Description

```
\label{template} \begin{tabular}{ll} template < typename T > \\ class & qpp::internal::Singleton < T > \\ \end{tabular}
```

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

To implement a singleton, derive your class from qpp::internal::Singleton, make qpp::internal::Singleton a friend of your class, then declare the constructor and destructor of your class as private. To get an instance, use the static member function qpp::internal::Singleton::get_instance() (qpp::internal::Singleton::get_thread_local_instance()), which returns a reference (thread_local_reference) to your newly created singleton (thread-safe in C++11).

Example:

See also

Code of qpp::Codes, qpp::Gates, qpp::Init, qpp::RandomDevices, qpp::States or qpp.h for real world examples of usage.

7.66.2 Constructor & Destructor Documentation

```
7.66.2.1 Singleton() [1/2]
template<typename T>
qpp::internal::Singleton < T >::Singleton ( ) [protected], [default], [noexcept]
7.66.2.2 Singleton() [2/2]
template<typename T>
qpp::internal::Singleton < T >::Singleton (
            const Singleton< T > \& ) [protected], [delete]
7.66.2.3 ∼Singleton()
template<typename T>
virtual qpp::internal::Singleton< T >::~Singleton ( ) [protected], [virtual], [default]
7.66.3 Member Function Documentation
7.66.3.1 get_instance()
template<typename T>
\texttt{static T\& qpp::internal::Singleton} < \texttt{T} > :: \texttt{get\_instance ()} \quad \texttt{[inline], [static], [noexcept]}
7.66.3.2 get_thread_local_instance()
template<typename T>
static T& qpp::internal::Singleton< T >::get_thread_local_instance ( ) [inline], [static],
[noexcept]
7.66.3.3 operator=()
template<typename T>
Singleton& qpp::internal::Singleton< T >::operator= (
              const Singleton< T > \& ) [protected], [delete]
```

The documentation for this class was generated from the following file:


• internal/classes/singleton.h

7.67 qpp::exception::SizeMismatch Class Reference


Size mismatch exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SizeMismatch:



Collaboration diagram for qpp::exception::SizeMismatch:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.67.1 Detailed Description

Size mismatch exception.

Sizes do not match

7.67.2 Member Function Documentation

7.67.2.1 description()

std::string qpp::exception::SizeMismatch::description () const [inline], [override], [virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.67.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where Text representing where the exception occurred

The documentation for this class was generated from the following file:

· classes/exception.h

7.68 qpp::NoiseType::StateDependent Class Reference

Template tag, used whenever the noise is state-dependent.

#include <classes/noise.h>

7.68.1 Detailed Description

Template tag, used whenever the noise is state-dependent.

The documentation for this class was generated from the following file:

· classes/noise.h

7.69 qpp::NoiseType::StateIndependent Class Reference

Template tag, used whenever the noise is state-independent.

#include <classes/noise.h>

7.69.1 Detailed Description

Template tag, used whenever the noise is state-independent.

The documentation for this class was generated from the following file:


classes/noise.h

7.70 qpp::States Class Reference


const Singleton class that implements most commonly used states

#include <classes/states.h>

Inheritance diagram for qpp::States:



Collaboration diagram for qpp::States:



Public Member Functions

• ket mes (idx d=2) const

Maximally entangled state of 2 qudits.

• ket zero (idx n, idx d=2) const

Zero state of n qudits.

• ket one (idx n, idx d=2) const

One state of n qudits.

• ket jn (idx j, idx n, idx d=2) const

 $|j\rangle^{\otimes n}$ state of n qudits

• ket plus (idx n) const

Plus state of n qubits.

• ket minus (idx n) const

Minus state of n qubits.

Public Attributes

```
    ket x0 {ket::Zero(2)}
```

Pauli Sigma-X 0-eigenstate |+>

ket x1 {ket::Zero(2)}

Pauli Sigma-X 1-eigenstate |->

ket y0 {ket::Zero(2)}

Pauli Sigma-Y 0-eigenstate |y+>

ket y1 {ket::Zero(2)}

Pauli Sigma-Y 1-eigenstate | y->

ket z0 {ket::Zero(2)}

Pauli Sigma-Z 0-eigenstate |0>

ket z1 {ket::Zero(2)}

Pauli Sigma-Z 1-eigenstate | 1>

cmat px0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

• cmat px1 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.

```
    cmat py0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 0-eigenstate |y+\rangle < y+|.

    cmat py1 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.

    cmat pz0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
• cmat pz1 {cmat::Zero(2, 2)}
      Projector onto the Pauli Sigma-Z 1-eigenstate | 1><1|.
ket b00 {ket::Zero(4)}
      Bell-00 state, as described in Nielsen and Chuang.

    ket b01 {ket::Zero(4)}

      Bell-01 state, as described in Nielsen and Chuang.

    ket b10 {ket::Zero(4)}

      Bell-10 state, as described in Nielsen and Chuang.
ket b11 {ket::Zero(4)}
      Bell-11 state, as described in Nielsen and Chuang.

    cmat pb00 {cmat::Zero(4, 4)}

      Projector onto the Bell-00 state.

    cmat pb01 {cmat::Zero(4, 4)}

      Projector onto the Bell-01 state.

    cmat pb10 {cmat::Zero(4, 4)}

      Projector onto the Bell-10 state.

    cmat pb11 {cmat::Zero(4, 4)}

      Projector onto the Bell-11 state.
ket GHZ {ket::Zero(8)}
      GHZ state.

    ket W {ket::Zero(8)}

      W state.
cmat pGHZ {cmat::Zero(8, 8)}
      Projector onto the GHZ state.
```

Private Member Functions

- States ()
- ∼States ()=default

Default destructor.

cmat pW {cmat::Zero(8, 8)}
 Projector onto the W state.

Friends

class internal::Singleton < const States >

Additional Inherited Members

7.70.1 Detailed Description

const Singleton class that implements most commonly used states

7.70.2 Constructor & Destructor Documentation

```
7.70.2.1 States()

qpp::States::States ( ) [inline], [private]

Initialize the states

7.70.2.2 ~States()

qpp::States::~States ( ) [private], [default]
```

7.70.3 Member Function Documentation

```
7.70.3.1 jn()
```

Default destructor.

 $|j\rangle^{\otimes n}$ state of *n* qudits

Parameters

j	Non-negative integer
n	Non-negative integer
d	Subsystem dimensions

Returns

 $|j\rangle^{\otimes n}$ state of *n* qudits

7.70.3.2 mes()

```
ket qpp::States::mes (
idx d = 2 ) const [inline]
```

Maximally entangled state of 2 qudits.

Parameters

d Subsystem dimensions

Returns

Maximally entangled state $\frac{1}{\sqrt{d}} \sum_{j=0}^{d-1} |jj\rangle$ of 2 qudits

7.70.3.3 minus()

```
ket qpp::States::minus (
          idx n ) const [inline]
```

Minus state of n qubits.

Parameters

```
n Non-negative integer
```

Returns

Minus state $|-\rangle^{\otimes n}$ of n qubits

7.70.3.4 one()

```
ket qpp::States::one (
          idx n,
          idx d = 2) const [inline]
```

One state of *n* qudits.

Parameters

n	Non-negative integer
d	Subsystem dimensions

Returns

One state $|1\rangle^{\otimes n}$ of n qudits

```
7.70.3.5 plus()
```

```
ket qpp::States::plus (
         idx n ) const [inline]
```

Plus state of *n* qubits.

Parameters

```
n Non-negative integer
```

Returns

Plus state $|+\rangle^{\otimes n}$ of n qubits

7.70.3.6 zero()

```
ket qpp::States::zero (
         idx n,
         idx d = 2 ) const [inline]
```

Zero state of *n* qudits.

Parameters

n	Non-negative integer
d	Subsystem dimensions

Returns

Zero state $|0\rangle^{\otimes n}$ of n qudits

7.70.4 Friends And Related Function Documentation

```
7.70.4.1 internal::Singleton < const States >
```

```
friend class internal::Singleton< const States > [friend]
```

7.70.5 Member Data Documentation

```
7.70.5.1 b00
```

```
ket qpp::States::b00 {ket::Zero(4)}
```

Bell-00 state, as described in Nielsen and Chuang.

```
7.70.5.2 b01
```

```
ket qpp::States::b01 {ket::Zero(4)}
```

Bell-01 state, as described in Nielsen and Chuang.

```
7.70.5.3 b10
```

```
ket qpp::States::b10 {ket::Zero(4)}
```

Bell-10 state, as described in Nielsen and Chuang.

7.70.5.4 b11

```
ket qpp::States::b11 {ket::Zero(4)}
```

Bell-11 state, as described in Nielsen and Chuang.

7.70.5.5 GHZ

```
ket qpp::States::GHZ {ket::Zero(8)}
```

GHZ state.

7.70.5.6 pb00

```
cmat qpp::States::pb00 {cmat::Zero(4, 4)}
```

Projector onto the Bell-00 state.

```
7.70.5.7 pb01
cmat qpp::States::pb01 {cmat::Zero(4, 4)}
Projector onto the Bell-01 state.
7.70.5.8 pb10
cmat qpp::States::pb10 {cmat::Zero(4, 4)}
Projector onto the Bell-10 state.
7.70.5.9 pb11
cmat qpp::States::pb11 {cmat::Zero(4, 4)}
Projector onto the Bell-11 state.
7.70.5.10 pGHZ
cmat qpp::States::pGHZ {cmat::Zero(8, 8)}
Projector onto the GHZ state.
7.70.5.11 pW
cmat qpp::States::pW {cmat::Zero(8, 8)}
Projector onto the W state.
7.70.5.12 px0
```

cmat qpp::States::px0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

```
7.70.5.13 px1
cmat qpp::States::px1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.
7.70.5.14 py0
cmat qpp::States::py0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 0-eigenstate |y+>< y+|.
7.70.5.15 py1
cmat qpp::States::py1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.
7.70.5.16 pz0
cmat qpp::States::pz0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
7.70.5.17 pz1
cmat qpp::States::pz1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 1-eigenstate |1><1|.
7.70.5.18 W
ket qpp::States::W {ket::Zero(8)}
```

W state.

```
7.70.5.19 x0
ket qpp::States::x0 {ket::Zero(2)}
Pauli Sigma-X 0-eigenstate |+>
7.70.5.20 x1
ket qpp::States::x1 {ket::Zero(2)}
Pauli Sigma-X 1-eigenstate |->
7.70.5.21 y0
ket qpp::States::y0 {ket::Zero(2)}
Pauli Sigma-Y 0-eigenstate |y+>
7.70.5.22 y1
ket qpp::States::y1 {ket::Zero(2)}
Pauli Sigma-Y 1-eigenstate |y->
7.70.5.23 z0
ket qpp::States::z0 {ket::Zero(2)}
Pauli Sigma-Z 0-eigenstate |0>
7.70.5.24 z1
ket qpp::States::z1 {ket::Zero(2)}
Pauli Sigma-Z 1-eigenstate |1>
The documentation for this class was generated from the following file:
```

Generated by Doxygen


· classes/states.h

7.71 qpp::exception::SubsysMismatchDims Class Reference


Subsystems mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SubsysMismatchDims:



Collaboration diagram for qpp::exception::SubsysMismatchDims:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.71.1 Detailed Description

Subsystems mismatch dimensions exception.

std::vector<idx> of subsystem labels has duplicates, or has entries that are larger than the size of the std← ::vector<idx> of dimensions

7.71.2 Member Function Documentation

7.71.2.1 description()

std::string qpp::exception::SubsysMismatchDims::description () const [inline], [override],
[virtual]

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.71.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred

The documentation for this class was generated from the following file:


classes/exception.h

7.72 qpp::Timer < T, CLOCK_T > Class Template Reference


Chronometer.

#include <classes/timer.h>

Inheritance diagram for qpp::Timer < T, CLOCK_T >:



Collaboration diagram for qpp::Timer < T, CLOCK_T >:



Public Member Functions

• Timer () noexcept

Constructs an instance with the current time as the starting point.

• virtual \sim Timer ()=default

Default virtual destructor.

· void tic () noexcept

Resets the chronometer.

· const Timer & toc () noexcept

Stops the chronometer.

• double tics () const noexcept

Time passed in the duration specified by T.

• template<typename U = T>

U get_duration () const noexcept

Duration specified by U.

Protected Attributes

- CLOCK_T::time_point start_
- CLOCK_T::time_point end_

Private Member Functions

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display() override*

7.72.1 Detailed Description

```
template < typename\ T = std::chrono::duration < double >, typename\ CLOCK\_T = std::chrono::steady\_clock > class\ qpp::Timer < T,\ CLOCK\_T >
```

Chronometer.

Template Parameters

T	Tics duration, default is std::chrono::duration <double>, i.e. seconds in double precision</double>
CLOCK⊷	Clock's type, default is std::chrono::steady_clock, not affected by wall clock changes during runtime
_ <i>T</i>	

7.72.2 Constructor & Destructor Documentation

7.72.2.1 Timer()

```
 \begin{tabular}{ll} template < typename T = std::chrono::duration < double>, typename CLOCK_T = std::chrono::steady &clock> \\ qpp::Timer < T, CLOCK_T >::Timer ( ) [inline], [noexcept] \\ \end{tabular}
```

Constructs an instance with the current time as the starting point.

7.72.2.2 \sim Timer()

Default virtual destructor.

7.72.3 Member Function Documentation

7.72.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream the number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc()

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.72.3.2 get_duration()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady 
_clock>
template<typename U = T>
U qpp::Timer< T, CLOCK_T >::get_duration ( ) const [inline], [noexcept]
```

Duration specified by U.

Template Parameters

U Duration, default is T, which defaults to std::chrono::duration<double>, i.e. seconds in double precision

Returns

Duration that passed between the instantiation/reset and invocation of qpp::Timer::toc()

7.72.3.3 tic()

Resets the chronometer.

Resets the starting/ending point to the current time

7.72.3.4 tics()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
double qpp::Timer< T, CLOCK_T >::tics ( ) const [inline], [noexcept]
```

Time passed in the duration specified by T.

Returns

Number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc()

7.72.3.5 toc()

```
\label{lock-type-ame} $$ $$ template<typename T = std::chrono::steady \leftarrow \_clock> $$ const Timer& qpp::Timer< T, CLOCK_T >::toc ( ) [inline], [noexcept] $$
```

Stops the chronometer.

Set the current time as the ending point

Returns

Reference to the current instance

7.72.4 Member Data Documentation

7.72.4.1 end

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::end_ [protected]
```

7.72.4.2 start_

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::start_ [protected]
```

The documentation for this class was generated from the following file:


· classes/timer.h

7.73 qpp::exception::TypeMismatch Class Reference


Type mismatch exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::TypeMismatch:



Collaboration diagram for qpp::exception::TypeMismatch:



Public Member Functions

- std::string description () const override
 - Exception description.
- Exception (const std::string &where)

Constructs an exception.

7.73.1 Detailed Description

Type mismatch exception.

Scalar types do not match

7.73.2 Member Function Documentation

7.73.2.1 description()

std::string qpp::exception::TypeMismatch::description () const [inline], [override], [virtual]
Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.73.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


• classes/exception.h

7.74 qpp::exception::UndefinedType Class Reference


Not defined for this type exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::UndefinedType:



Collaboration diagram for qpp::exception::UndefinedType:



Public Member Functions

- std::string description () const override
 - Exception description.
- Exception (const std::string &where)

Constructs an exception.

7.74.1 Detailed Description

Not defined for this type exception.

Templated specialization is not defined for this type

7.74.2 Member Function Documentation

7.74.2.1 description()

std::string qpp::exception::UndefinedType::description () const [inline], [override], [virtual]
Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.74.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:


• classes/exception.h

7.75 qpp::exception::Unknown Class Reference


Unknown exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Unknown:



Collaboration diagram for qpp::exception::Unknown:



Public Member Functions

- std::string description () const override
 - Exception description.
- Exception (const std::string &where)

Constructs an exception.

7.75.1 Detailed Description

Unknown exception.

Thrown when no other exception is suitable (not recommended, it is better to define another suitable exception type)

7.75.2 Member Function Documentation

7.75.2.1 description()

std::string qpp::exception::Unknown::description () const [inline], [override], [virtual]
Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.75.2.2 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

Parameters

where	,	Text representing where the exception occurred]
-------	---	--	---


The documentation for this class was generated from the following file:

· classes/exception.h


7.76 qpp::QCircuit::iterator::value_type_ Class Reference

Value type class for qpp::QCircuit::iterator.

Inheritance diagram for qpp::QCircuit::iterator::value_type_:



Collaboration diagram for qpp::QCircuit::iterator::value_type_:



Public Member Functions

```
    value_type_ (const QCircuit *value_type_qc)
        Default value_type_ constructor.
    value_type_ (const value_type_ &)=default
        Default copy constructor.
    value_type_ & operator= (const value_type_ &)=default
        Default copy assignment operator.
```

Public Attributes

```
    const QCircuit * value_type_qc_
        < non-owning pointer to the grand-parent const quantum circuit</li>
    StepType type_{StepType::NONE}
        step type
    idx ip_{static_cast<idx>(-1)}
        instruction pointer
    std::vector< GateStep >::const_iterator gates_ip_{gates instruction pointer}
    std::vector< MeasureStep >::const_iterator measurements_ip_{measurements instruction pointer}
```

Private Member Functions

7.76.1 Detailed Description

Value type class for qpp::QCircuit::iterator.

7.76.2 Constructor & Destructor Documentation

Parameters

```
value_type_qc | Pointer to constant quantum circuit
```

Default copy constructor.

7.76.3 Member Function Documentation

7.76.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream the textual representation of the iterator de-referenced element

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.76.3.2 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

7.76.4 Member Data Documentation

```
7.76.4.1 gates_ip_
std::vector<GateStep>::const_iterator qpp::QCircuit::iterator::value_type_::gates_ip_ {}
gates instruction pointer
7.76.4.2 ip_
idx qpp::QCircuit::iterator::value_type_::ip_ {static_cast<idx>(-1)}
instruction pointer
7.76.4.3 measurements_ip_
\verb|std::vector<| MeasureStep>::const_iterator | qpp::QCircuit::iterator::value_type_::measurements\_{\leftarrow}| terator| | terat
measurements instruction pointer
7.76.4.4 type_
StepType qpp::QCircuit::iterator::value_type_::type_ {StepType::NONE}
step type
7.76.4.5 value_type_qc_
const QCircuit* qpp::QCircuit::iterator::value_type_::value_type_qc_
 < non-owning pointer to the grand-parent const quantum circuit
The documentation for this class was generated from the following file:
```

• classes/circuits/circuits.h


360 Class Documentation

7.77 qpp::exception::ZeroSize Class Reference


Object has zero size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::ZeroSize:



Collaboration diagram for qpp::exception::ZeroSize:



Public Member Functions

• std::string description () const override

Exception description.

• Exception (const std::string &where)

Constructs an exception.

7.77.1 Detailed Description

Object has zero size exception.

Zero sized object, e.g. empty Eigen::Matrix or std::vector with no elements

7.77.2 Member Function Documentation

7.77.2.1 description()

```
std::string qpp::exception::ZeroSize::description ( ) const [inline], [override], [virtual]
```

Exception description.

Returns

Exception description

Implements qpp::exception::Exception.

7.77.2.2 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

Parameters

where	Text representing where the exception occurred
-------	--

The documentation for this class was generated from the following file:

· classes/exception.h

362 Class Documentation


Chapter 8

File Documentation

8.1 classes/circuits/circuits.h File Reference

Qudit quantum circuits.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::QCircuit

Quantum circuit class.

• struct qpp::QCircuit::GateStep

One step consisting only of gates/operators in the circuit.

• struct qpp::QCircuit::MeasureStep

One step consisting only of measurements in the circuit.

· class qpp::QCircuit::iterator

Quantum circuit bound-checking (safe) iterator.

• class qpp::QCircuit::iterator::value_type_

Value type class for qpp::QCircuit::iterator.

Namespaces

• qpp

Quantum++ main namespace.


8.1.1 Detailed Description

Qudit quantum circuits.

8.2 classes/circuits/engines.h File Reference

Qudit quantum engines.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::QEngine

Quantum circuit engine, executes qpp::QCircuit.

class qpp::QNoisyEngine < NoiseModel >

Noisy quantum circuit engine, executes qpp::QCircuit.

Namespaces

• qpp

Quantum++ main namespace.


8.2.1 Detailed Description

Qudit quantum engines.

8.3 classes/codes.h File Reference

Quantum error correcting codes.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::Codes

const Singleton class that defines quantum error correcting codes

Namespaces

• qpp

Quantum++ main namespace.

8.3.1 Detailed Description

Quantum error correcting codes.

8.4 classes/exception.h File Reference

Exceptions.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::exception::Exception

Base class for generating Quantum++ custom exceptions.

· class qpp::exception::Unknown

Unknown exception.

class qpp::exception::ZeroSize

Object has zero size exception.

class gpp::exception::MatrixNotSquare

Matrix is not square exception.

· class qpp::exception::MatrixNotCvector

Matrix is not a column vector exception.

class qpp::exception::MatrixNotRvector

Matrix is not a row vector exception.

class qpp::exception::MatrixNotVector

Matrix is not a vector exception.

class qpp::exception::MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

• class qpp::exception::MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

class qpp::exception::MatrixNotSquareNorVector

Matrix is not square nor vector exception.

class qpp::exception::MatrixMismatchSubsys

Matrix mismatch subsystems exception.

· class qpp::exception::DimsInvalid

Invalid dimension(s) exception.

· class qpp::exception::DimsNotEqual

Dimensions not equal exception.

class qpp::exception::DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

· class qpp::exception::DimsMismatchCvector

Dimension(s) mismatch column vector size exception.

class qpp::exception::DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

class qpp::exception::DimsMismatchVector

Dimension(s) mismatch vector size exception.

class qpp::exception::SubsysMismatchDims

Subsystems mismatch dimensions exception.

class qpp::exception::PermInvalid

Invalid permutation exception.

· class qpp::exception::PermMismatchDims

Permutation mismatch dimensions exception.

class qpp::exception::NotQubitMatrix

Matrix is not 2 x 2 exception.

· class qpp::exception::NotQubitCvector

Column vector is not 2 x 1 exception.

class qpp::exception::NotQubitRvector

Row vector is not 1 x 2 exception.

class qpp::exception::NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

class qpp::exception::NotQubitSubsys

Subsystems are not qubits exception.

· class qpp::exception::NotBipartite

Not bi-partite exception.

· class qpp::exception::NoCodeword

Codeword does not exist exception.

class qpp::exception::OutOfRange

Argument out of range exception.

class qpp::exception::TypeMismatch

Type mismatch exception.

• class qpp::exception::SizeMismatch

Size mismatch exception.

class qpp::exception::UndefinedType

Not defined for this type exception.

• class qpp::exception::QuditAlreadyMeasured

Qudit was already measured exception.

class qpp::exception::Duplicates

System (e.g. std::vector) has duplicates exception.

class qpp::exception::CustomException

Custom exception.

· class qpp::exception::NotImplemented

Code not yet implemented.

· class qpp::exception::InvalidIterator

Invalid iterator.

Namespaces

• qpp

Quantum++ main namespace.

• qpp::exception

Quantum++ exception hierarchy namespace.


8.4.1 Detailed Description

Exceptions.

8.5 classes/gates.h File Reference

Quantum gates.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::Gates

const Singleton class that implements most commonly used gates

Namespaces

• qpp

Quantum++ main namespace.

8.5.1 Detailed Description

Quantum gates.

8.6 classes/idisplay.h File Reference

Display interface via the non-virtual interface (NVI) and very basic JSON serialization support interface.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

· class qpp::IJSON

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

Namespaces

• qpp

Quantum++ main namespace.


8.6.1 Detailed Description

Display interface via the non-virtual interface (NVI) and very basic JSON serialization support interface.

8.7 classes/init.h File Reference

Initialization.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::Init

const Singleton class that performs additional initializations/cleanups

Namespaces

• qpp

Quantum++ main namespace.


8.7.1 Detailed Description

Initialization.

8.8 classes/noise.h File Reference

Noise models.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::NoiseType

Contains template tags used to specify the noise type.

class qpp::NoiseBase< T >

Base class for all noise models, derive your particular noise model.

• class qpp::QubitDepolarizingNoise

Qubit depolarizing noise.

• class qpp::QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

· class qpp::QubitBitFlipNoise

Qubit bit flip noise.

· class qpp::QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

 $\bullet \ \ class \ qpp:: Qubit Amplitude Damping Noise \\$

Qubit amplitude damping noise, as described in Nielsen and Chuang.

• class qpp::QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

· class qpp::QuditDepolarizingNoise

Qudit depolarizing noise.

Namespaces

• qpp

Quantum++ main namespace.


8.8.1 Detailed Description

Noise models.

8.9 classes/random_devices.h File Reference

Random devices.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::RandomDevices

Singleton class that manages the source of randomness in the library.

Namespaces

qpp

Quantum++ main namespace.


8.9.1 Detailed Description

Random devices.

8.10 classes/reversible.h File Reference

Support for classical reversible circuits.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::Dynamic_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime.

class qpp::Bit_circuit

Classical reversible circuit simulator.

Namespaces

• qpp

Quantum++ main namespace.


8.10.1 Detailed Description

Support for classical reversible circuits.

8.11 classes/states.h File Reference

Quantum states.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::States

const Singleton class that implements most commonly used states

Namespaces

qpp

Quantum++ main namespace.

8.11.1 Detailed Description

Quantum states.

8.12 classes/timer.h File Reference

Timing.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::Timer < T, CLOCK_T >
 Chronometer.

Namespaces

• qpp

Quantum++ main namespace.


8.12.1 Detailed Description

Timing.

8.13 constants.h File Reference

Constants.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

· qpp::literals

Enumerations

enum { qpp::RES, qpp::PROB, qpp::ST }
 Constants to be used by std::get<> on the result of qpp::measure(), qpp_measure_seq() etc.

Functions

- constexpr cplx qpp::literals::operator"" _i (unsigned long long int x) noexcept
 - User-defined literal for complex $i = \sqrt{-1}$ (integer overload)
- constexpr cplx qpp::literals::operator"" _i (long double x) noexcept
 - User-defined literal for complex $i = \sqrt{-1}$ (real overload)
- constexpr std::complex< float > qpp::literals::operator""_if (unsigned long long int x) noexcept
 - User-defined literal for complex $i=\sqrt{-1}$ (integer overload)
- constexpr std::complex< float > qpp::literals::operator"" _if (long double x) noexcept
 - User-defined literal for complex $i = \sqrt{-1}$ (real overload)
- cplx qpp::omega (idx D)

D-th root of unity.

Variables

• constexpr double qpp::chop = 1e-16

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

• constexpr idx qpp::maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

• constexpr double qpp::pi = 3.141592653589793238462643383279502884

 π

• constexpr double qpp::ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

• constexpr double qpp::infty = std::numeric_limits<double>::max()

Used to denote infinity in double precision.


8.13.1 Detailed Description

Constants.

8.14 entanglement.h File Reference

Entanglement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

```
template<typename Derived >
  dyn col vect< double > gpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector<
  idx > &dims)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  dyn_col_vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  cmat qpp::schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat <a href="mailto:qpp::schmidtA">qpp::schmidtA</a> (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Bob side.
template<typename Derived >
  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Bob side.
• template<typename Derived >
  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx
  > &dims)
      Schmidt probabilities of the bi-partite pure state A.

    template<typename Derived >

  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt probabilities of the bi-partite pure state A.

    template<typename Derived >

  double qpp::entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Entanglement of the bi-partite pure state A.
• template<typename Derived >
  double <a href="mailto:qpp::entanglement">qpp::entanglement</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Entanglement of the bi-partite pure state A.

    template<typename Derived >

  double <a href="mailto:qpp::gconcurrence">qpp::gconcurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      G-concurrence of the bi-partite pure state A.

    template<typename Derived >

  double qpp::negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double <a href="mailto:qpp::negativity">qpp::negativity</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Logarithmic negativity of the bi-partite mixed state A.
template<typename Derived >
  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double <a href="mailto:qpp::concurrence">qpp::concurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.
```


8.14.1 Detailed Description

Entanglement functions.

8.15 entropies.h File Reference

Entropy functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

```
    template < typename Derived >
        double qpp::entropy (const Eigen::MatrixBase < Derived > &A)
```

von-Neumann entropy of the density matrix A

double qpp::entropy (const std::vector< double > &prob)

Shannon entropy of the probability distribution prob.

 $\bullet \ \ \mathsf{template} \mathord{<} \mathsf{typename} \ \mathsf{Derived} >$

```
double <a href="mailto:qpp::renyi">qpp::renyi</a> (const Eigen::MatrixBase< Derived > &A, double alpha)
```

Renyi- α entropy of the density matrix A, for $\alpha \geq 0$.

double qpp::renyi (const std::vector< double > &prob, double alpha)

Renyi- α entropy of the probability distribution prob, for $\alpha \geq 0.$

template<typename Derived >

```
double qpp::tsallis (const Eigen::MatrixBase< Derived > &A, double q)
```

Tsallis- q entropy of the density matrix A, for $q \geq 0$.

double qpp::tsallis (const std::vector< double > &prob, double q)

Tsallis- q entropy of the probability distribution prob, for $q \geq 0$.

• template<typename Derived >

double qpp::qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const std::vector< idx > &subsysB, const std::vector< idx > &dims)

Quantum mutual information between 2 subsystems of a composite system.

• template<typename Derived >

 $\label{lem:double qpp::qmutualinfo} \ (const \ Eigen:: Matrix Base < Derived > \&A, const \ std:: vector < idx > \&subsysA, const \ std:: vector < idx > \&subsysB, idx \ d=2)$

Quantum mutual information between 2 subsystems of a composite system.

8.15.1 Detailed Description

Entropy functions.

8.16 experimental/experimental.h File Reference

Experimental/test functions/classes.

Namespaces

• qpp

Quantum++ main namespace.

• qpp::experimental

Experimental/test functions/classes, do not use or modify.


8.16.1 Detailed Description

Experimental/test functions/classes.

8.17 functions.h File Reference

Generic quantum computing functions.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::internal::HashEigen

Functor for hashing Eigen expressions.

• class qpp::internal::EqualEigen

Functor for comparing Eigen expressions for equality.

Namespaces

qpp

Quantum++ main namespace.

- · qpp::literals
- qpp::internal

Internal utility functions, do not use them directly or modify them.

Functions

```
    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::transpose (const Eigen::MatrixBase< Derived > &A)
      Transpose.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::adjoint (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::inverse (const Eigen::MatrixBase< Derived > &A)
      Inverse.

    template<typename Derived >

  Derived::Scalar qpp::trace (const Eigen::MatrixBase< Derived > &A)
      Trace.
• template<typename Derived >
  Derived::Scalar qpp::det (const Eigen::MatrixBase< Derived > &A)
      Determinant.

    template<typename Derived >

  Derived::Scalar <a href="mailto:qpp::logdet">qpp::logdet</a> (const Eigen::MatrixBase</a> Derived > &A)
     Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar <a href="mailto:qpp::sum">qpp::sum</a> (const Eigen::MatrixBase< Derived > &A)
      Element-wise sum of A.
• template<typename Derived >
  Derived::Scalar <a href="mailto:open:prod">open:prod</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise product of A.

    template<typename Derived >

  double <a href="mailto:qpp::norm">qpp::norm</a> (const Eigen::MatrixBase< Derived > &A)
     Frobenius norm.

    template < typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::normalize (const Eigen::MatrixBase< Derived > &A)
     Normalizes state vector (column or row vector) or density matrix.
template<typename Derived >
  std::pair< dyn_col_vect< cplx >, cmat > qpp::eig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition.
ullet template<typename Derived >
  dyn_col_vect< cplx > qpp::evals (const Eigen::MatrixBase< Derived > &A)
     Eigenvalues.

    template<typename Derived >

  cmat qpp::evects (const Eigen::MatrixBase< Derived > &A)
```

Eigenvectors.

```
• template<typename Derived >
  std::pair< dyn_col_vect< double >, cmat > qpp::heig (const Eigen::MatrixBase< Derived > &A)
     Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > qpp::hevals (const Eigen::MatrixBase< Derived > &A)
     Hermitian eigenvalues.
• template<typename Derived >
  cmat qpp::hevects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors of Hermitian matrix.

    template<typename Derived >

  std::tuple< cmat, dyn col vect< double >, cmat > qpp::svd (const Eigen::MatrixBase< Derived > &A)
     Full singular value decomposition.
• template<typename Derived >
  dyn_col_vect< double > qpp::svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.
• template<typename Derived >
  cmat qpp::svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.
template<typename Derived >
  cmat qpp::svdV (const Eigen::MatrixBase< Derived > &A)
     Right singular vectors.

    template<typename Derived >

  cmat qpp::funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)
• template<typename Derived >
  cmat qpp::sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.
• template<typename Derived >
  cmat qpp::absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.

    template<typename Derived >

  cmat qpp::expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.
• template<typename Derived >
  cmat qpp::logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.
• template<typename Derived >
  cmat qpp::sinm (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  cmat qpp::cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.

    template<typename Derived >

  cmat qpp::spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::powm (const Eigen::MatrixBase< Derived > &A, idx n)
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

    template<typename Derived >

  double qpp::schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > qpp::cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const
  typename Derived::Scalar &))
```

```
Functor.
```

```
• template<typename T >
```

dyn_mat< typename T::Scalar > qpp::kron (const T &head)

Kronecker product.

• template<typename T , typename... Args>

dyn_mat< typename T::Scalar > qpp::kron (const T &head, const Args &... tail)

Kronecker product.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::kron (const std::vector< Derived > &As)

Kronecker product.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::kron (const std::initializer_list< Derived > &As)

Kronecker product.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::kronpow (const Eigen::MatrixBase< Derived > &A, idx n)

Kronecker power.

template<typename T >

dyn_mat< typename T::Scalar > qpp::dirsum (const T &head)

Direct sum.

• template<typename T , typename... Args>

dyn_mat< typename T::Scalar > qpp::dirsum (const T &head, const Args &... tail)

Direct sum

ullet template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::vector< Derived > &As)

Direct sum.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::initializer_list< Derived > &As)

Direct sum.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)

Direct sum power.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::reshape (const Eigen::MatrixBase< Derived > &A, idx rows, idx cols)

Reshape.

- template<typename Derived1 , typename Derived2 >

 $\label{localize} $$ dyn_mat< typename Derived1::Scalar > qpp::comm (const Eigen::MatrixBase< Derived1 > \&A, const Eigen::MatrixBase< Derived2 > \&B) $$$

Commutator.

- template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::anticomm (const Eigen::MatrixBase< Derived1 > &A, const Eigen::MatrixBase< Derived2 > &B)

Anti-commutator.

ullet template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::prj (const Eigen::MatrixBase< Derived > &A)

Projector

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::grams (const std::vector< Derived > &As)

Gram-Schmidt orthogonalization.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::grams (const std::initializer_list< Derived > &As)

Gram-Schmidt orthogonalization.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::grams (const Eigen::MatrixBase< Derived > &A)

Gram-Schmidt orthogonalization.

std::vector< idx > qpp::n2multiidx (idx n, const std::vector< idx > &dims)

Non-negative integer index to multi-index.

idx qpp::multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

Multi-index to non-negative integer index.

ket qpp::mket (const std::vector< idx > &mask, const std::vector< idx > &dims)

Multi-partite qudit ket.

ket qpp::mket (const std::vector< idx > &mask, idx d=2)

Multi-partite qudit ket.

cmat qpp::mprj (const std::vector < idx > &mask, const std::vector < idx > &dims)

Projector onto multi-partite qudit ket.

cmat qpp::mprj (const std::vector< idx > &mask, idx d=2)

Projector onto multi-partite qudit ket.

• template<typename InputIterator >

std::vector< double > qpp::abssq (InputIterator first, InputIterator last)

Computes the absolute values squared of an STL-like range of complex numbers.

• template<typename Container >

std::vector< double > qpp::abssq (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Computes the absolute values squared of an STL-like container.

template<typename Derived >

```
std::vector< double > qpp::abssq (const Eigen::MatrixBase< Derived > &A)
```

Computes the absolute values squared of an Eigen expression.

template<typename InputIterator >

std::iterator_traits< InputIterator >::value_type qpp::sum (InputIterator first, InputIterator last)

Element-wise sum of an STL-like range.

template<typename Container >

Container::value_type qpp::sum (const Container &c, typename std::enable_if< is_iterable< Container >
::value >::type *=nullptr)

Element-wise sum of the elements of an STL-like container.

• template<typename InputIterator >

std::iterator traits< InputIterator >::value type qpp::prod (InputIterator first, InputIterator last)

Element-wise product of an STL-like range.

• template<typename Container >

Container::value_type qpp::prod (const Container &c, typename std::enable_if< is_iterable< Container >
::value >::type *=nullptr)

Element-wise product of the elements of an STL-like container.

• template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > qpp::rho2pure (const Eigen::MatrixBase< Derived > &A)
```

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

std::vector< idx > qpp::complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

template<typename Derived >

```
std::vector< double > qpp::rho2bloch (const Eigen::MatrixBase< Derived > &A)
```

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat qpp::bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

template<char... Bits>

```
ket qpp::literals::operator"" _ket ()
```

Multi-partite qubit ket user-defined literal.

template<char... Bits>

```
bra qpp::literals::operator"" _bra ()
```

Multi-partite qubit bra user-defined literal.

template<char... Bits>
 cmat qpp::literals::operator"" _prj ()

Multi-partite qubit projector user-defined literal.

template < class T > void qpp::internal::hash_combine (std::size_t &seed, const T &v)

Hash combine.

template<typename Derived >
 std::size_t qpp::hash_eigen (const Eigen::MatrixBase< Derived > &A, std::size_t seed=0)

Computes the hash of en Eigen matrix/vector/expression.


8.17.1 Detailed Description

Generic quantum computing functions.

8.18 input_output.h File Reference

Input/output functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

- template < typename Derived >
 internal::IOManipEigen qpp::disp (const Eigen::MatrixBase < Derived > &A, double chop=qpp::chop)
 Eigen expression ostream manipulator.
- internal::IOManipEigen qpp::disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

template<typename InputIterator >
 internal::IOManipRange< InputIterator > qpp::disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)

Range ostream manipulator.

template<typename Container>
 internal::IOManipRange< typename Container::const_iterator > qpp::disp (const Container &c, const std
 ::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop, typename
 std::enable if< is iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

template<typename PointerType >
 internal::IOManipPointer< PointerType > qpp::disp (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]", double chop=qpp::chop)

C-style pointer ostream manipulator.

ullet template<typename Derived >

void qpp::save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.


8.18.1 Detailed Description

Input/output functions.

8.19 instruments.h File Reference

Measurement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)

Generalized inner product.

ullet template<typename Derived >

dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

template<typename Derived >

std::tuple < std::vector < idx >, double, cmat $> qpp::measure_seq$ (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template<typename Derived >
 std::tuple< std::vector< idx >, double, cmat > qpp::measure_seq (const Eigen::MatrixBase< Derived > &A,
 std::vector< idx > target, idx d=2)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.


8.19.1 Detailed Description

Measurement functions.

8.20 internal/classes/iomanip.h File Reference

Input/output manipulators.

This graph shows which files directly or indirectly include this file:



Classes

- class qpp::internal::IOManipRange
 InputIterator >
- class qpp::internal::IOManipPointer< PointerType >
- class qpp::internal::IOManipEigen

Namespaces

• qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


8.20.1 Detailed Description

Input/output manipulators.

8.21 internal/classes/singleton.h File Reference

Singleton pattern via CRTP.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::internal::Singleton< T >

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Namespaces

qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


8.21.1 Detailed Description

Singleton pattern via CRTP.

8.22 internal/util.h File Reference

Internal utility functions.

This graph shows which files directly or indirectly include this file:



Classes

• struct qpp::internal::Display_Impl_

Namespaces

• qpp

Quantum++ main namespace.

qpp::internal

Internal utility functions, do not use them directly or modify them.

Functions

- void qpp::internal::n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx qpp::internal::multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- template<typename Derived >
 bool qpp::internal::check_square_mat (const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
 bool qpp::internal::check_vector (const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
 bool qpp::internal::check_rvector (const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
 bool qpp::internal::check_cvector (const Eigen::MatrixBase< Derived > &A)
- template<typename T >
 bool qpp::internal::check_nonzero_size (const T &x) noexcept
- template<typename T1, typename T2 >
 bool qpp::internal::check_matching_sizes (const T1 &lhs, const T2 &rhs) noexcept
- bool qpp::internal::check_dims (const std::vector< idx > &dims)
- template<typename Derived >
 bool qpp::internal::check_dims_match_mat (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)
- template<typename Derived >
 bool qpp::internal::check_dims_match_cvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- template<typename Derived >
 bool qpp::internal::check_dims_match_rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)
- bool qpp::internal::check_eq_dims (const std::vector< idx > &dims, idx dim) noexcept
- bool qpp::internal::check no duplicates (std::vector< idx > v)
- bool qpp::internal::check_subsys_match_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)
- template<typename Derived >
 bool qpp::internal::check_qubit_matrix (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
 bool qpp::internal::check_qubit_cvector (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
 bool qpp::internal::check_qubit_rvector (const Eigen::MatrixBase< Derived > &A) noexcept
- template<typename Derived >
 bool qpp::internal::check_qubit_vector (const Eigen::MatrixBase< Derived > &A) noexcept
- bool qpp::internal::check_perm (const std::vector < idx > &perm)
 template < typename Derived1 , typename Derived2 >
- dyn_mat< typename Derived1::Scalar > qpp::internal::kron2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::MatrixBase< Derived2 > &B)
- template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::internal::dirsum2 (const Eigen::MatrixBase< Derived1 > &A,
 const Eigen::MatrixBase< Derived2 > &B)
- template<typename T >
 void qpp::internal::variadic_vector_emplace (std::vector< T > &)
- template<typename T, typename First, typename... Args>
 void qpp::internal::variadic_vector_emplace (std::vector< T > &v, First &&first, Args &&... args)
- idx qpp::internal::get_num_subsys (idx D, idx d)
- idx qpp::internal::get_dim_subsys (idx sz, idx N)
- template<typename T, typename std::enable_if< std::numeric_limits< T >::is_iec559||is_complex< T >::value >::type * = nullptr> T qpp::internal::abs chop (const T &x, double chop=qpp::chop)
- template<typename T, typename std::enable_if<!(std::numeric_limits< T >::is_iec559||is_complex< T >::value)>::type * = nullptr>
 T qpp::internal::abs_chop (const T &x, double QPP_UNUSED_chop=qpp::chop)

8.22.1 Detailed Description

Internal utility functions.

8.23 MATLAB/matlab.h File Reference

Input/output interfacing with MATLAB.

```
#include "mat.h"
#include "mex.h"
```

Namespaces

qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< cplx > ::type
 qpp::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::← Scalar > >::type qpp::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.


8.23.1 Detailed Description

Input/output interfacing with MATLAB.

8.24 number theory.h File Reference

Number theory functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

std::vector< int > qpp::x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double qpp::contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

• bigint qpp::gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint qpp::gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint qpp::lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint qpp::lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > qpp::invperm (const std::vector< idx > &perm)

Inverse permutation.

std::vector< idx > qpp::compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

std::vector< bigint > qpp::factors (bigint a)

Prime factor decomposition.

• bigint qpp::modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

• bigint qpp::modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple < bigint, bigint, bigint > qpp::egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint qpp::modinv (bigint a, bigint p)

Modular inverse of a mod p.

• bool qpp::isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

• bigint qpp::randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

• std::vector< std::pair< int, int > > qpp::convergents (const std::vector< int > &cf)

Convergents.

std::vector< std::pair< int, int > > qpp::convergents (double x, idx N)

Convergents.


8.24.1 Detailed Description

Number theory functions.

8.25 operations.h File Reference

Quantum operation functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 const std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 idx d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const
 Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const
 Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)

 $\textit{Applies the gate A to the part target of the multi-partite state vector or density \textit{matrix state}.}$

template<typename Derived >
 cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

template<typename Derived >
 cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std
 ::vector< idx > &target, const std::vector< idx > &dims)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

• template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std ::vector< idx > &target, idx d=2)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat qpp::kraus2super (const std::vector< cmat > &Ks)

Superoperator matrix.

cmat gpp::kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector< cmat > qpp::choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat qpp::choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat qpp::super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace2 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptrace (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Partial transpose.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2)

Partial transpose.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &perm, const std::vector< idx > &dims)

Subsystem permutation.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &perm, idx d=2)

Subsystem permutation.

template<typename Derived >
 dyn_mat< typename Derived::Scalar > qpp::applyQFT (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

```
dyn_mat< typename Derived::Scalar > qpp::applyTFQ (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)
```

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > qpp::TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)
```

Inverse (adjoint) qudit quantum Fourier transform.

template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > qpp::QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)
```

Qudit quantum Fourier transform.

8.25.1 Detailed Description

Quantum operation functions.

8.26 qpp.h File Reference

Quantum++ main header file, includes all other necessary headers.

```
#include <algorithm>
#include <cassert>
#include <chrono>
#include <cmath>
#include <complex>
#include <cstdlib>
#include <cstring>
#include <exception>
#include <fstream>
#include <functional>
#include <initializer_list>
#include <iomanip>
#include <iterator>
#include <limits>
#include <memory>
#include <numeric>
#include <ostream>
#include <random>
#include <sstream>
#include <stdexcept>
#include <string>
#include <tuple>
#include <type_traits>
#include <unordered_map>
#include <utility>
#include <vector>
#include <Eigen/Dense>
```

```
#include <Eigen/SVD>
#include "types.h"
#include "classes/exception.h"
#include "constants.h"
#include "traits.h"
#include "classes/idisplay.h"
#include "internal/util.h"
#include "internal/classes/iomanip.h"
#include "input_output.h"
#include "internal/classes/singleton.h"
#include "classes/random_devices.h"
#include "random.h"
#include "number_theory.h"
#include "functions.h"
#include "classes/init.h"
#include "classes/codes.h"
#include "classes/gates.h"
#include "classes/states.h"
#include "statistics.h"
#include "operations.h"
#include "entropies.h"
#include "entanglement.h"
#include "classes/timer.h"
#include "instruments.h"
#include "classes/reversible.h"
#include "classes/noise.h"
#include "classes/circuits/circuits.h"
#include "classes/circuits/engines.h"
```

Namespaces

• qpp

Quantum++ main namespace.

Macros

• #define QPP_UNUSED_

8.26.1 Detailed Description

Quantum++ main header file, includes all other necessary headers.

8.26.2 Macro Definition Documentation

```
8.26.2.1 QPP_UNUSED_
```


#define QPP_UNUSED_

396 File Documentation

8.27 random.h File Reference

Randomness-related functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

• double qpp::rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

bigint qpp::rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx qpp::randidx (idx a=std::numeric_limits < idx >::min(), idx b=std::numeric_limits < idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

• template<typename Derived >

Derived qpp::rand (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double a QPP_UNUSED_=0, double b QPP_UNUSED_=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

template<>

dmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

• template<>

cmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived qpp::randn (idx rows QPP_UNUSED_, idx cols QPP_UNUSED_, double mean QPP_UNUSED_=0, double sigma QPP_UNUSED_=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

dmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

• template<>

cmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

double qpp::randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

cmat qpp::randU (idx D=2)

Generates a random unitary matrix.

cmat qpp::randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > qpp::randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat qpp::randH (idx D=2)

Generates a random Hermitian matrix.

ket qpp::randket (idx D=2)

Generates a random normalized ket (pure state vector)

• cmat qpp::randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > qpp::randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > qpp::randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.


8.27.1 Detailed Description

Randomness-related functions.

8.28 statistics.h File Reference

Statistics functions.

This graph shows which files directly or indirectly include this file:



398 File Documentation

Namespaces

• qpp

Quantum++ main namespace.

Functions

std::vector< double > qpp::uniform (idx N)

Uniform probability distribution vector.

std::vector< double > qpp::marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > qpp::marginalY (const dmat &probXY)

Marginal distribution.

• template<typename Container >

double qpp::avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_ \leftarrow iterable< Container >::value >::type *=nullptr)

Average.

• template<typename Container >

double qpp::cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Covariance.

• template<typename Container >

double qpp::var (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_ \leftarrow iterable< Container >::value >::type *=nullptr)

Variance.

• template<typename Container >

double qpp::sigma (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_ \leftarrow iterable< Container >::value >::type *=nullptr)

Standard deviation.

• template<typename Container >

double qpp::cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if is_iterable Container >::value >::type *=nullptr)

Correlation.

8.28.1 Detailed Description


Statistics functions.

8.29 traits.h File Reference

Type traits.

8.29 traits.h File Reference 399

This graph shows which files directly or indirectly include this file:



Classes

```
    struct qpp::make_void < Ts >
        Helper for qpp::to_void <> alias template.
```

struct qpp::is_iterable < T, typename >

Checks whether T is compatible with an STL-like iterable container.

• struct qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(*(std::declval < T >().end()), decltyp

struct qpp::is_matrix_expression< Derived >

Checks whether the type is an Eigen matrix expression.

struct qpp::is_complex< T >

Checks whether the type is a complex type.

struct qpp::is_complex< std::complex< T >>

Checks whether the type is a complex number type, specialization for complex types.

Namespaces

• qpp

Quantum++ main namespace.

Typedefs

```
    template < typename... Ts>
        using qpp::to_void = typename make_void < Ts... > ::type
        Alias template that implements the proposal for void_t.
```

8.29.1 Detailed Description


Type traits.

400 File Documentation

8.30 types.h File Reference

Type aliases.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Typedefs

• using qpp::idx = std::size_t

Non-negative integer index, make sure you use an unsigned type.

• using qpp::bigint = long long int

Big integer.

• using qpp::cplx = std::complex< double >

Complex number in double precision.

• using qpp::ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector.

• using qpp::bra = Eigen::RowVectorXcd

Complex (double precision) dynamic Eigen row vector.

• using qpp::cmat = Eigen::MatrixXcd

Complex (double precision) dynamic Eigen matrix.

• using qpp::dmat = Eigen::MatrixXd

Real (double precision) dynamic Eigen matrix.

 $\bullet \ \ \text{template}{<} \text{typename Scalar} >$

using qpp::dyn_mat = Eigen::Matrix< Scalar, Eigen::Dynamic, Eigen::Dynamic >

Dynamic Eigen matrix over the field specified by Scalar.

• template<typename Scalar >

```
using qpp::dyn_col_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 >
```

Dynamic Eigen column vector over the field specified by Scalar.

• template<typename Scalar >

```
using <a href="mailto:qpp::dyn_row_vect">qpp::dyn_row_vect</a> = Eigen::Matrix< Scalar, 1, Eigen::Dynamic >
```

Dynamic Eigen row vector over the field specified by Scalar.

8.30.1 Detailed Description

Type aliases.

Index

\sim Bit_circuit	qpp::Dynamic_bitset, 161
qpp::Bit_circuit, 132	apply
~Codes	qpp, 31–33
qpp::Codes, 139	applyCTRL
~Dynamic_bitset	qpp, 34
qpp::Dynamic_bitset, 161	applyQFT
~Gates	qpp, 35
qpp::Gates, 176	applyTFQ
~IDisplay	qpp, 35
qpp::IDisplay, 190	avg
∼IJSON	qpp, 36
qpp::IJSON, 192	
~Init	b00
qpp::Init, 194	qpp::States, 339
~NoiseBase	b01
qpp::NoiseBase, 241	qpp::States, 340
~QCircuit	b10
qpp::QCircuit, 273	qpp::States, 340
~QEngine	b11
qpp::QEngine, 300	qpp::States, 340
~RandomDevices	bCNOT
gpp::RandomDevices, 327	qpp::Bit_circuit, 136
~Singleton	bFRED
qpp::internal::Singleton, 331	qpp::Bit_circuit, 136
~States	bNOT
qpp::States, 337	qpp::Bit_circuit, 136
~Timer	bSWAP
qpp::Timer, 347	qpp::Bit_circuit, 136
чрртипот, 047	bTOF
A	qpp::Bit circuit, 136
qpp::internal::IOManipEigen, 198	begin
abs_chop	qpp::QCircuit, 275
qpp::internal, 120	bigint
absm	qpp, 26
qpp, 29	Bit_circuit
abssq	qpp::Bit_circuit, 131
qpp, 29, 30	bloch2rho
add_dit	qpp, 36
qpp::QCircuit, 273	bra
add_hash_	qpp, 26
qpp::QCircuit, 274	btotal
add_qudit	_
qpp::QCircuit, 274	qpp::Bit_circuit, 136
adjoint	c reg
•	qpp::QCircuit::MeasureStep, 23
qpp, 30	cCTRL custom
all	-
qpp::Dynamic_bitset, 161	qpp::QCircuit, 277
anticomm	cCTRL
qpp, 31	qpp::QCircuit, 275–277
any	CNOTba

qpp::Gates, 183	qpp::internal::IOManipRange, 204
CNOT	classes/circuits/circuits.h, 363
qpp::Bit_circuit, 132	classes/circuits/engines.h, 364
qpp::Gates, 183	classes/codes.h, 365
CTRL_custom	classes/exception.h, 365
qpp::QCircuit, 280	classes/gates.h, 367
CTRL	classes/idisplay.h, 368
qpp::Gates, 176	classes/init.h, 369
qpp::QCircuit, 278, 279	classes/noise.h, 370
cbegin	classes/random_devices.h, 371
qpp::QCircuit, 275	classes/reversible.h, 371
cend	classes/states.h, 372
qpp::QCircuit, 278	classes/timer.h, 373
check_cvector	cmat
qpp::internal, 121	qpp, 27
check_dims	cmat_hash_tbl_
qpp::internal, 121	qpp::QCircuit, 295
check_dims_match_cvect	Codes
qpp::internal, 121	qpp::Codes, 139
check_dims_match_mat	codeword
qpp::internal, 121	qpp::Codes, 139
check_dims_match_rvect	comm
qpp::internal, 121	qpp, 38
check_eq_dims	complement
qpp::internal, 121	qpp, 38
check_matching_sizes	compperm
qpp::internal, 122	qpp, 39
check_no_duplicates	compute_probs_
qpp::internal, 122	qpp::NoiseBase, 241
check_nonzero_size	compute_state_
qpp::internal, 122	qpp::NoiseBase, 241
check_perm	concurrence
qpp::internal, 122	qpp, 39
check_qubit_cvector	conjugate
qpp::internal, 122	qpp, 39
check_qubit_matrix	const_iterator
qpp::internal, 122	qpp::QCircuit, 271
check_qubit_rvector	constants.h, 374
qpp::internal, 123	contfrac2x
check_qubit_vector	qpp, 40
qpp::internal, 123	convergents
check_rvector	qpp, 40, 41
qpp::internal, 123	cor
check_square_mat	qpp, 41
qpp::internal, 123	cosm
check_subsys_match_dims	qpp, 42
qpp::internal, 123	count
check_vector	qpp::Dynamic_bitset, 161
qpp::internal, 123	count_
choi2kraus	qpp::Bit_circuit, 136
qpp, 37	qpp::QCircuit, 295
choi2super	COV
qpp, 37	qpp, 42
chop	cplx
qpp, 116	qpp, 27
chop_	ctrl_
qpp::internal::IOManipEigen, 198	qpp::QCircuit::GateStep, 187
qpp::internal::IOManipPointer, 201	CustomException

qpp::excep	tion::CustomException, 141		qpp, 45
cwise		disp)
qpp, 43		•	qpp, 46, 47
CZ		disp	
qpp::Gates	: 184		qpp::Dynamic bitset, 162
عاداده ما داره	,		qpp::IDisplay, 190
d_			qpp::QCircuit, 280
qpp::Noise	Base, 245		qpp::QCircuit; 250 qpp::QCircuit::iterator::value_type_, 358
qpp::QCirc			
data	,		qpp::QEngine, 300
	mic_bitset, 161		qpp::Timer, 348
depth_			qpp::internal::IOManipEigen, 198
qpp::Bit ci	rouit 137		qpp::internal::IOManipPointer, 200
—	icuit, 137		qpp::internal::IOManipRange, 204
description	tions Overtons Exposition 140	disp	olay_impl_
	tion::CustomException, 142		qpp::internal::Display_Impl_, 155
	tion::DimsInvalid, 144	dits	=
	tion::DimsMismatchCvector, 146		qpp::QEngine, 307
	tion::DimsMismatchMatrix, 148	dma	at
	tion::DimsMismatchRvector, 150		qpp, 27
dbb::exceb	tion::DimsMismatchVector, 152	dyn	_col_vect
qpp::excep	tion::DimsNotEqual, 154	, .	 qpp, 27
qpp::excep	tion::Duplicates, 157	dvn	_mat
qpp::excep	tion::Exception, 172	<i>∞</i> ,	qpp, 27
qpp::excep	tion::InvalidIterator, 196	dyn	row_vect
	tion::MatrixMismatchSubsys, 218	uyn	
	tion::MatrixNotCvector, 221	Dun	qpp, 28
	tion::MatrixNotRvector, 223	Dyn	amic_bitset
	tion::MatrixNotSquare, 225		qpp::Dynamic_bitset, 160
	tion::MatrixNotSquareNorCvector, 227	ee	
	tion::MatrixNotSquareNorSvector, 229	CC	app. 116
	•	000	qpp, 116
	tion::MatrixNotSquareNorVector, 231	egc	
	tion::MatrixNotVector, 233		qpp, 48
	tion::NoCodeword, 237	eig	
	tion::NotBipartite, 248		qpp, 48
	tion::NotImplemented, 250	elen	-
	tion::NotQubitCvector, 252		qpp::QCircuit::iterator, 216
dbb::exceb	tion::NotQubitMatrix, 254	end	
qpp::excep	tion::NotQubitRvector, 256		qpp::QCircuit, 281
qpp::excep	tion::NotQubitSubsys, 258	end	_
qpp::excep	tion::NotQubitVector, 260		qpp::Timer, 349
qpp::excep	tion::OutOfRange, 262		qpp::internal::IOManipPointer, 201
qpp::excep	tion::PermInvalid, 264		qpp::internal::IOManipRange, 205
	tion::PermMismatchDims, 266	enta	anglement
	tion::QuditAlreadyMeasured, 322		qpp, 49
	tion::SizeMismatch, 333	enta	anglement.h, 375
	tion::SubsysMismatchDims, 345		opies.h, 377
	tion::TypeMismatch, 351	entr	•
	tion::UndefinedType, 353	enu	• •
	• •		qpp, 50
	tion::Unknown, 355	eval	
	tion::ZeroSize, 361		qpp, 51
det		eve	
qpp, 43		_	qpp, 51
difference_type		Exc	eption
qpp::QCirc	uit::iterator, 212		qpp::exception::DimsInvalid, 144
dirsum			qpp::exception::DimsMismatchCvector, 146
qpp, 43–45	5		qpp::exception::DimsMismatchMatrix, 148
dirsum2			qpp::exception::DimsMismatchRvector, 150
qpp::intern	al, 124		qpp::exception::DimsMismatchVector, 152
dirsumpow			qpp::exception::DimsNotEqual, 154
•			

qpp::exception::Duplicates, 157	gate
qpp::exception::Exception, 172	qpp::QCircuit, 281, 282
qpp::exception::InvalidIterator, 196	gate_custom
qpp::exception::MatrixMismatchSubsys, 219	qpp::QCircuit, 283
qpp::exception::MatrixNotCvector, 221	gate_fan
qpp::exception::MatrixNotRvector, 223	qpp::QCircuit, 283, 284
qpp::exception::MatrixNotSquare, 225	gate_hash_
qpp::exception::MatrixNotSquareNorCvector, 227	qpp::QCircuit::GateStep, 187
qpp::exception::MatrixNotSquareNorRvector, 229	gate_type_
qpp::exception::MatrixNotSquareNorVector, 231	qpp::QCircuit::GateStep, 188
qpp::exception::MatrixNotVector, 233	GateStep
qpp::exception::NoCodeword, 237	qpp::QCircuit::GateStep, 187
qpp::exception::NotBipartite, 248	GateType
qpp::exception::NotImplemented, 250	
qpp::exception::NotQubitCvector, 252	qpp::QCircuit, 271
qpp::exception::NotQubitMatrix, 254	Gates
qpp::exception::NotQubitRvector, 256	qpp::Gates, 176
qpp::exception::NotQubitNector, 250 qpp::exception::NotQubitSubsys, 258	gates_
qpp::exception::NotQubitVector, 260	qpp::QCircuit, 295
qpp::exception::NotQubit vector, 200 qpp::exception::OutOfRange, 262	gates_ip_
qpp::exception::OttOrkange, 202 qpp::exception::PermInvalid, 264	qpp::QCircuit::iterator::value_type_, 358
	gcd
app::exception::PermMismatchDims, 266	qpp, 53
qpp::exception::QuditAlreadyMeasured, 323	gconcurrence
qpp::exception::SizeMismatch, 333	qpp, 54
qpp::exception::SubsysMismatchDims, 345	generated_
<pre>qpp::exception::TypeMismatch, 351 qpp::exception::UndefinedType, 353</pre>	qpp::NoiseBase, 245
	get
qpp::exception::Unknown, 355	qpp::Dynamic_bitset, 163
qpp::exception::ZeroSize, 361 execute	get_Ks
qpp::QEngine, 301	qpp::NoiseBase, 242
qpp::QNoisyEngine, 310, 311	get_circuit
expandout	qpp::QEngine, 301
qpp::Gates, 177, 178	get_cmat_hash_tbl_
experimental/experimental.h, 378	qpp::QCircuit, 284
expm	get_d
qpp, 52	qpp::NoiseBase, 242
4pp, 02	qpp::QCircuit, 284
FRED	get_dim_subsys
qpp::Bit_circuit, 132	qpp::internal, 124
qpp::Gates, 184	get_dit
factors	qpp::QEngine, 302
qpp, 52	get_dits
Fd	qpp::QEngine, 302
qpp::Gates, 179	get_duration
fill_Ks_	qpp::Timer, 348
qpp::QuditDepolarizingNoise, 325	get_gate_count
fill_probs_	qpp::Bit_circuit, 133
qpp::QuditDepolarizingNoise, 325	qpp::QCircuit, 285
first_	get_gate_depth
qpp::internal::IOManipRange, 205	qpp::Bit_circuit, 133
flip	qpp::QCircuit, 285
qpp::Dynamic_bitset, 162	get_gates_
functions.h, 378	qpp::QCircuit, 286
funm	get_instance
qpp, 52	qpp::internal::Singleton, 331
0117	get_last_idx
GHZ	qpp::NoiseBase, 242
qpp::States, 340	get_last_K

qpp::NoiseBase, 243	IOManipPointer
get_last_p	qpp::internal::IOManipPointer, 200
qpp::NoiseBase, 243	IOManipRange
get_measured	qpp::internal::IOManipRange, 203, 204
qpp::QCircuit, 286	ld
qpp::QEngine, 302, 303	qpp::Gates, 179
get_measurement_count	ld2
qpp::QCircuit, 286, 287	qpp::Gates, 184
get_measurements_	idx
qpp::QCircuit, 287	qpp, 28
get_name	index_
qpp::Gates, 179	qpp::Dynamic_bitset, 163
qpp::QCircuit, 287	infty
get_nc	qpp, 116
qpp::QCircuit, 287	Init
get_noise_results	qpp::Init, 194
qpp::QNoisyEngine, 311	input_output.h, 383
get_non_measured	instruments.h, 384
qpp::QCircuit, 288	internal/classes/iomanip.h, 386
qpp::QEngine, 303	internal/classes/singleton.h, 387
get_nop_count	internal/util.h, 387
qpp::QCircuit, 288	internal::Singleton< const Codes >
get_nq	qpp::Codes, 139
qpp::QCircuit, 288	internal::Singleton< const Gates >
get_num_subsys	qpp::Gates, 183
qpp::internal, 124	internal::Singleton< const Init >
get_prng	qpp::Init, 194
qpp::RandomDevices, 328	internal::Singleton< const States >
get_probs	qpp::States, 339
qpp::NoiseBase, 243	internal::Singleton < RandomDevices >
qpp::QEngine, 303	qpp::RandomDevices, 329
get_psi	inverse
qpp::QEngine, 303	qpp, 57
get_relative_pos_	invperm
qpp::QEngine, 304	qpp, 58
get_step_count	ip
qpp::QCircuit, 288	qpp, 58, 59
get_thread_local_instance	ip_
qpp::internal::Singleton, 331	qpp::QCircuit::iterator::value_type_, 359
grams 54.55	isprime
qpp, 54, 55	qpp, 59
Н	iterator
qpp::Gates, 184	qpp::QCircuit::iterator, 213
hash_combine	iterator_category
qpp::internal, 124	qpp::QCircuit::iterator, 212
hash_eigen	jn
qpp, 55	qpp::States, 337
heig	qppstatos, 557
qpp, 56	ket
hevals	qpp, 28
qpp, 56	kraus2choi
hevects	qpp, 59
qpp, 57	kraus2super
11°1° / °	qpp, 60
i_	kron
qpp::NoiseBase, 245	qpp, 60, 62, 63
IOManipEigen	kron2
qpp::internal::IOManipEigen, 198	qpp::internal, 125
· ·	

kronnow	app. 76, 77
kronpow	qpp, 76, 77 modiny
qpp, 63 Ks	
-	qpp, 77
qpp::NoiseBase, 245	modmul
last	qpp, 78
-	modpow
qpp::internal::IOManipRange, 205	qpp, 78
lcm	mprj
qpp, 64	qpp, 79
load	msg_
qpp, 65	qpp::exception::Exception, 173
qpp::RandomDevices, 328	multiidx2n
loadMATLAB	qpp, 80
qpp, 65, 66	qpp::internal, 125
logdet	
qpp, 67	n2multiidx
logm	qpp, 80
qpp, 67	qpp::internal, 125
lognegativity	N_
qpp, 67, 69	qpp::internal::IOManipPointer, 201
11.17	n
MATLAB/matlab.h, 389	qpp::Dynamic_bitset, 168
MODMUL	NOT
qpp::Gates, 180	qpp::Bit_circuit, 134
marginalX	
qpp, 69	name_
marginalY	qpp::QCircuit, 296
qpp, 69	qpp::QCircuit::GateStep, 188
	qpp::QCircuit::MeasureStep, 235
mats_hash_	nc_
qpp::QCircuit::MeasureStep, 235	qpp::QCircuit, 296
maxn	negativity
qpp, 116	qpp, 81
measure	noise_
qpp, 70–74	qpp::QNoisyEngine, 311
measure_seq	noise_results_
qpp, 75, 76	qpp::QNoisyEngine, 312
MeasureStep	noise_type
qpp::QCircuit::MeasureStep, 234, 235	qpp::NoiseBase, 240
MeasureType	NoiseBase
qpp::QCircuit, 272	qpp::NoiseBase, 240
measured_	none
qpp::QCircuit, 295	qpp::Dynamic_bitset, 163
measurement_count_	nop
qpp::QCircuit, 296	qpp::QCircuit, 290
measurement_type_	norm
qpp::QCircuit::MeasureStep, 235	qpp, 82
measurements_	normalize
qpp::QCircuit, 296	
	qpp, 82
measurements_ip_	nq_
qpp::QCircuit::iterator::value_type_, 359	qpp::QCircuit, 296
measureV	number_theory.h, 390
qpp::QCircuit, 289	-#+
measureZ	offset_
qpp::QCircuit, 290	qpp::Dynamic_bitset, 164
mes	omega
qpp::States, 337	qpp, <mark>82</mark>
minus	one
qpp::States, 338	qpp::States, 338
mket	operations.h, 392

operator!=	prng_
qpp::Dynamic_bitset, 164	qpp::RandomDevices, 329
qpp::QCircuit::iterator, 213	probs_
operator<<	qpp::NoiseBase, 245
qpp::IDisplay, 191	qpp::QEngine, 307
qpp::QCircuit, 293, 294	prod
operator*	qpp, 84
qpp::QCircuit::iterator, 214	psi_
operator()	qpp::QEngine, 307
qpp::NoiseBase, 243, 244	ptrace
qpp::internal::EqualEigen, 169	qpp, 85
qpp::internal::HashEigen, 189	ptrace1
operator++	qpp, 86
qpp::QCircuit::iterator, 214	ptrace2
operator-	qpp, 87
qpp::Dynamic_bitset, 164	ptranspose
operator=	qpp, 88 pW
qpp::QCircuit::iterator, 214	•
<pre>qpp::QCircuit::iterator::value_type_, 358 qpp::QEngine, 304</pre>	qpp::States, 341
	px0
qpp::internal::IOManipPointer, 201 qpp::internal::IOManipRange, 204	qpp::States, 341 px1
qpp::internal::Singleton, 331	qpp::States, 341
operator==	py0
qpp::Dynamic_bitset, 165	qpp::States, 342
qpp::QCircuit::iterator, 215	py1
operator""_bra	qpp::States, 342
qpp::literals, 126	pz0
operator""_i	qpp::States, 342
qpp::literals, 126, 127	pz1
operator""_if	qpp::States, 342
qpp::literals, 127	qppotatoo, 012
operator""_ket	QCircuit
qpp::literals, 127	qpp::QCircuit, 273
operator"" _prj	QEngine
qpp::literals, 128	qpp::QCircuit, 295
qppto:s.o, :=o	qpp::QEngine, 299, 300
p_	QFT
qpp::internal::IOManipPointer, 201	qpp, 89
pGHZ	qpp::QCircuit, 290, 291
qpp::States, 341	QNoisyEngine
pb00	qpp::QNoisyEngine, 310
qpp::States, 340	QPP_UNUSED_
pb01	qpp.h, 395
qpp::States, 340	qc_
pb10	qpp::QCircuit::iterator, 216
qpp::States, 341	qpp::QEngine, 307
pb11	qmutualinfo
qpp::States, 341	qpp, 89, 90
pi	qpp, 13
qpp, 117	absm, 29
plus	abssq, 29, 30
qpp::States, 338	adjoint, 30
pointer	anticomm, 31
qpp::QCircuit::iterator, 212	apply, 31–33
powm	applyCTRL, 34
qpp, 83	applyQFT, 35
prj	applyTFQ, 35
qpp, 83	avg, 36

bigint, 26	logdet, 67
bloch2rho, 36	logm, <mark>67</mark>
bra, 26	lognegativity, 67, 69
choi2kraus, 37	marginalX, 69
choi2super, 37	marginalY, 69
chop, 116	maxn, 116
cmat, 27	measure, 70-74
comm, 38	measure_seq, 75, 76
complement, 38	mket, 76, 77
compperm, 39	modinv, 77
concurrence, 39	modmul, 78
conjugate, 39	modpow, 78
contfrac2x, 40	mprj, <mark>79</mark>
convergents, 40, 41	multiidx2n, 80
cor, 41	n2multiidx, 80
cosm, 42	negativity, 81
cov, 42	norm, 82
cplx, 27	normalize, 82
cwise, 43	omega, 82
det, 43	pi, 117
dirsum, 43–45	powm, 83
dirsumpow, 45	prj, <mark>83</mark>
disp, 46, 47	prod, 84
dmat, 27	ptrace, 85
dyn_col_vect, 27	ptrace1, 86
dyn_mat, 27	ptrace2, 87
dyn_row_vect, 28	ptranspose, 88
ee, 116	QFT, 89
egcd, 48	qmutualinfo, 89, 90
eig, 48	rand, 90-92
entanglement, 49	randH, 93
entropy, 50	randidx, 93
evals, 51	randket, 93
evects, 51	randkraus, 94
expm, 52	randn, 94–96
factors, 52	randperm, 96
funm, 52	randprime, 97
gcd, 53	randprob, 97
gconcurrence, 54	randrho, 97
grams, 54, 55	randU, 98
hash_eigen, 55	randV, 98
heig, 56	renyi, 98, 99
hevals, 56	reshape, 99
hevects, 57	rho2bloch, 100
idx, 28	rho2pure, 100
infty, 116	save, 101
inverse, 57	saveMATLAB, 101, 102
invperm, 58	schatten, 103
ip, 58, 59	schmidtA, 103
isprime, 59	schmidtB, 104
ket, 28	schmidtcoeffs, 105
kraus2choi, 59	schmidtprobs, 106
kraus2super, 60	sigma, 107
kron, 60, 62, 63	sinm, 107
kronpow, 63	spectralpowm, 107
Icm, 64	sqrtm, 108
load, 65	ST, 29
loadMATLAB, 65, 66	sum, 108, 109
,,	,,

super2choi, 109	operator==, 165
svals, 110	rand, 165, 166
svd, 110	reset, 166
svdU, 111	set, 166, 167
svdV, 111	size, 167
syspermute, 111, 112	storage_size, 167
TFQ, 112	storage_size_, 168
to_void, 28	storage_type, 160
trace, 113	to_string, 167
transpose, 113	v_, 168
tsallis, 114	value type, 160
uniform, 115	qpp::Gates, 173
var, 115	~Gates, 176
x2contfrac, 115	CNOTba, 183
qpp.h, 394	CNOT, 183
QPP_UNUSED_, 395	CTRL, 176
	CZ, 184
qpp::Bit_circuit, 129	
~Bit_circuit, 132	expandout, 177, 178
bCNOT_, 136	FRED, 184
bFRED_, 136	Fd, 179
bNOT_, 136	Gates, 176
bSWAP_, 136	get_name, 179
bTOF_, 136	H, 184
Bit_circuit, 131	ld, 179
btotal_, 136	ld2, 184
CNOT, 132	internal::Singleton< const Gates >, 183
count_, 136	MODMUL, 180
depth_, 137	Rn, 180
FRED, 132	RX, 181
get_gate_count, 133	RY, 181
get_gate_depth, 133	RZ, 182
NOT, 134	S, 184
reset, 134	SWAPd, 182
SWAP, 134	SWAP, 184
TOF, 135	T, 185
X, 135	TOF, 185
qpp::Codes, 137	X, 185
\sim Codes, 139	Xd, 182
Codes, 139	Y, 185
codeword, 139	Z, 185
internal::Singleton < const Codes >, 139	Zd, 183
Type, 138	qpp::IDisplay, 189
qpp::Dynamic_bitset, 157	∼IDisplay, 190
~Dynamic_bitset, 161	display, 190
all, 161	operator<<, 191
any, 161	gpp::IJSON, 191
count, 161	~IJSON, 192
data, 161	to_JSON, 192
display, 162	qpp::Init, 192
Dynamic_bitset, 160	∼Init, 194
flip, 162	Init, 194
get, 163	internal::Singleton< const Init >, 194
index_, 163	qpp::NoiseBase
n_, 168	∼NoiseBase, 241
none, 163	compute_probs_, 241
offset_, 164	compute_state_, 241
operator!=, 164	d_, 245
operator-, 164	generated_, 245
οροιαίοι-, 10 1	generated_, 243

get_Ks, 242	measureZ, 290
get_d, 242	name_, 296
get_last_idx, 242	nc_, 296
get_last_K, 243	nop, 290
get_last_p, 243	nq_, 296
get_probs, 243	operator<<, 293, 294
i_, 245	QCircuit, 273
Ks_, 245	QEngine, 295
noise_type, 240	QFT, 290, 291
NoiseBase, 240	step_types_, 296
operator(), 243, 244	StepType, 272
probs_, 245	TFQ, 291, 292
qpp::NoiseBase< T >, 238	to_JSON, 293
qpp::NoiseType, 246	qpp::QCircuit::GateStep, 186
qpp::NoiseType::StateDependent, 334	ctrl_, 187
qpp::NoiseType::StateIndependent, 334	gate_hash_, 187
qpp::QCircuit, 267	gate_type_, 188
\sim QCircuit, 273	GateStep, 187
add_dit, 273	name_, 188
add_hash_, 274	target_, 188
add_qudit, 274	qpp::QCircuit::MeasureStep, 233
begin, 275	c_reg_, 235
cCTRL_custom, 277	mats hash , 235
cCTRL, 275–277	MeasureStep, 234, 235
CTRL_custom, 280	measurement_type_, 235
CTRL, 278, 279	name_, 235
cbegin, 275	target_, 236
cend, 278	qpp::QCircuit::iterator, 211
cmat_hash_tbl_, 295	difference_type, 212
const_iterator, 271	elem_, 216
count_, 295	iterator, 213
d , 295	iterator_category, 212
display, 280	operator!=, 213
end, 281	operator*, 214
gate, 281, 282	operator++, 214
gate custom, 283	operator=, 214
gate_fan, 283, 284	operator==, 215
GateType, 271	pointer, 212
gates_, 295	qc_, 216
get_cmat_hash_tbl_, 284	reference, 213
get_d, 284	set begin , 215
get gate count, 285	set_end_, 215
get_gate_depth, 285	value_type, 213
get_gates_, 286	qpp::QCircuit::iterator::value_type_, 356
get measured, 286	display, 358
get_measurement_count, 286, 287	gates_ip_, 358
get measurements , 287	ip_, 359
get_name, 287	measurements_ip_, 359
get_name, 207 get_nc, 287	operator=, 358
get_non_measured, 288	type_, 359
get_nop_count, 288	value_type_, 357, 358
get_nq, 288	value_type_qc_, 359
get_step_count, 288	qpp::QEngine, 297
MeasureType, 272	~QEngine, 300
measurement count 206	display, 300
measurementcount_, 296	dits_, 307
measureN 280	execute, 301
measureV, 289	get_circuit, 301

get_dit, 302	jn, 337
get_dits, 302	mes, 337
get_measured, 302, 303	minus, 338
get_non_measured, 303	one, 338
get_probs, 303	pGHZ, 341
get_psi, 303	pb00, 340
get_relative_pos_, 304	pb01, 340
operator=, 304	pb10, 341
probs_, 307	pb11, 341
psi_, 307	plus, 338
QEngine, 299, 300	pW, 341
qc_, 307	px0, 341
reset, 304	px1, 341
set_dit, 304	py0, 342
set measured , 306	py1, 342
set_psi, 306	pz0, 342
subsys_, 308	pz1, 342
to_JSON, 306	States, 337
qpp::QNoisyEngine	W, 342
execute, 310, 311	x0, 342
get_noise_results, 311	x1, 343
noise_, 311	y0, 343
noise_results_, 312	y1, 343
QNoisyEngine, 310	z0, 343
qpp::QNoisyEngine < NoiseModel >, 308	z1, 343
qpp::QubitAmplitudeDampingNoise, 312	zero, 339
QubitAmplitudeDampingNoise, 313	qpp::Timer
qpp::QubitBitFlipNoise, 314	∼Timer, 347
QubitBitFlipNoise, 315	display, 348
qpp::QubitBitPhaseFlipNoise, 315	end_, 349
QubitBitPhaseFlipNoise, 316	get_duration, 348
qpp::QubitDepolarizingNoise, 317	start_, 349
QubitDepolarizingNoise, 318	tic, 348
qpp::QubitPhaseDampingNoise, 318	tics, 349
QubitPhaseDampingNoise, 319	Timer, 347
qpp::QubitPhaseFlipNoise, 320	toc, 349
QubitPhaseFlipNoise, 321	qpp::Timer< T, CLOCK_T >, 346
qpp::QuditDepolarizingNoise, 323	qpp::exception, 117
fill_Ks_, 325	qpp::exception::CustomException, 140
fill_probs_, 325	CustomException, 141
QuditDepolarizingNoise, 324	description, 142
qpp::RandomDevices, 326	what_, 142
\sim RandomDevices, 327	qpp::exception::DimsInvalid, 143
get_prng, 328	description, 144
internal::Singleton < RandomDevices >, 329	Exception, 144
load, 328	qpp::exception::DimsMismatchCvector, 145
prng_, 329	description, 146
RandomDevices, 327	Exception, 146
rd_, 329	qpp::exception::DimsMismatchMatrix, 147
save, 328	description, 148
qpp::States, 334	Exception, 148
~States, 337	qpp::exception::DimsMismatchRvector, 149
b00, 339	description, 150
b01, 340	Exception, 150
b10, 340	qpp::exception::DimsMismatchVector, 151
b11, 340	description, 152
GHZ, 340	Exception, 152
internal::Singleton< const States >, 339	qpp::exception::DimsNotEqual, 153
	-II-I

decembration 454	Formation 050
description, 154	Exception, 258
Exception, 154	qpp::exception::NotQubitVector, 258
app::exception::Duplicates, 156	description, 260
description, 157	Exception, 260
Exception, 157	qpp::exception::OutOfRange, 260
app::exception::Exception, 170	description, 262
description, 172	Exception, 262
Exception, 172	qpp::exception::PermInvalid, 262
msg_, 173	description, 264
what, 172	Exception, 264
where_, 173	qpp::exception::PermMismatchDims, 264
qpp::exception::InvalidIterator, 194	description, 266
description, 196	Exception, 266
Exception, 196	qpp::exception::QuditAlreadyMeasured, 321
qpp::exception::MatrixMismatchSubsys, 217	description, 322
description, 218	Exception, 323
Exception, 219	qpp::exception::SizeMismatch, 332
qpp::exception::MatrixNotCvector, 219	description, 333
description, 221	Exception, 333
Exception, 221	qpp::exception::SubsysMismatchDims, 344
qpp::exception::MatrixNotRvector, 221	description, 345
description, 223	Exception, 345
Exception, 223	qpp::exception::TypeMismatch, 350
qpp::exception::MatrixNotSquare, 223	description, 351
description, 225	Exception, 351
Exception, 225	qpp::exception::UndefinedType, 352
qpp::exception::MatrixNotSquareNorCvector, 225	description, 353
description, 227	Exception, 353
Exception, 227	qpp::exception::Unknown, 354
qpp::exception::MatrixNotSquareNorRvector, 227	description, 355
description, 229	Exception, 355
Exception, 229	qpp::exception::ZeroSize, 360
qpp::exception::MatrixNotSquareNorVector, 229	description, 361
description, 231	Exception, 361
Exception, 231	qpp::experimental, 119
qpp::exception::MatrixNotVector, 231	qpp::internal, 119
	abs_chop, 120
description, 233 Exception, 233	_ ·
•	check_cvector, 121
app::exception::NoCodeword, 236	check_dims, 121
description, 237	check_dims_match_cvect, 121
Exception, 237	check_dims_match_mat, 121
qpp::exception::NotBipartite, 246	check_dims_match_rvect, 121
description, 248	check_eq_dims, 121
Exception, 248	check_matching_sizes, 122
qpp::exception::NotImplemented, 248	check_no_duplicates, 122
description, 250	check_nonzero_size, 122
Exception, 250	check_perm, 122
qpp::exception::NotQubitCvector, 250	check_qubit_cvector, 122
description, 252	check_qubit_matrix, 122
Exception, 252	check_qubit_rvector, 123
qpp::exception::NotQubitMatrix, 252	check_qubit_vector, 123
description, 254	check_rvector, 123
Exception, 254	check_square_mat, 123
qpp::exception::NotQubitRvector, 254	check_subsys_match_dims, 123
description, 256	check_vector, 123
Exception, 256	dirsum2, 124
qpp::exception::NotQubitSubsys, 256	get_dim_subsys, 124
description, 258	get_num_subsys, 124
•	- - - ·

hach combine 124	operator"" pri 129
hash_combine, 124	operator"" _prj, 128
kron2, 125	qpp::make_void
multiidx2n, 125	type, 217 qpp::make_void< Ts >, 216
n2multiidx, 125	QubitAmplitudeDampingNoise
variadic_vector_emplace, 125	qpp::QubitAmplitudeDampingNoise, 313
qpp::internal::Display_Impl_, 155	QubitBitFlipNoise
display_impl_, 155	qpp::QubitBitFlipNoise, 315
qpp::internal::EqualEigen, 169	QubitBitPhaseFlipNoise
operator(), 169	qpp::QubitBitPhaseFlipNoise, 316
qpp::internal::HashEigen, 188	QubitDepolarizingNoise
operator(), 189	qpp::QubitDepolarizingNoise, 318
qpp::internal::IOManipEigen, 196	QubitPhaseDampingNoise
A_, 198	qpp::QubitPhaseDampingNoise, 319
chop_, 198	QubitPhaseFlipNoise
display, 198	qpp::QubitPhaseFlipNoise, 321
IOManipEigen, 198	
qpp::internal::IOManipPointer	QuditDepolarizingNoise
chop_, 201	qpp::QuditDepolarizingNoise, 324
display, 200	rand
end_, 201	qpp, 90–92
IOManipPointer, 200	qpp::Dynamic_bitset, 165, 166
N_, 201	randH
operator=, 201	qpp, 93
p_, 201	randidx
separator_, 202	qpp, 93
start_, 202	randket
qpp::internal::IOManipPointer< PointerType >, 199	qpp, 93
qpp::internal::IOManipRange	randkraus
chop_, 204	qpp, 94
display, 204	randn
end_, 205	qpp, 94–96
first , 205	random.h, 396
IOManipRange, 203, 204	RandomDevices
last_, 205	qpp::RandomDevices, 327
operator=, 204	
separator_, 205	randperm
start_, 205	qpp, 96
qpp::internal::IOManipRange< InputIterator >, 202	randprime
qpp::internal::Singleton	qpp, 97 randprob
\sim Singleton, 331	
get_instance, 331	qpp, 97 randrho
get thread local instance, 331	
operator=, 331	qpp, 97 randU
Singleton, 330, 331	
qpp::internal::Singleton $<$ T $>$, 329	qpp, 98 randV
qpp::is_complex< std::complex< T > >, 207	
qpp::is_complex< T >, 206	qpp, 98
qpp::is_iterable< T, to_void< decltype(std::declval< T	rd_
$>$ ().begin()), decltype(std::declval< T >(). \leftrightarrow	qpp::RandomDevices, 329
	reference
end()), decltype(*(std::declval< T >().←	qpp::QCircuit::iterator, 213
begin()))>>, 209	renyi
qpp::is_iterable < T, typename >, 208	qpp, 98, 99
qpp::is_matrix_expression< Derived >, 210	reset
qpp::literals, 126	qpp::Bit_circuit, 134
operator"" _bra, 126	qpp::Dynamic_bitset, 166
operator"" _i, 126, 127	qpp::QEngine, 304
operator"" _if, 127	reshape
operator"" _ket, 127	qpp, 99

rho2bloch	qpp, 107
qpp, 100	sqrtm
rho2pure	qpp, 108
qpp, 100	ST
Rn	qpp, 29
qpp::Gates, 180	start_
RX	qpp::Timer, 349
qpp::Gates, 181	qpp::internal::IOManipPointer, 202
RY	qpp::internal::IOManipRange, 205
qpp::Gates, 181	States
RZ	qpp::States, 337
qpp::Gates, 182	statistics.h, 397
""	step_types_
S	qpp::QCircuit, 296
qpp::Gates, 184	StepType
SWAPd	qpp::QCircuit, 272
qpp::Gates, 182	storage_size
SWAP	qpp::Dynamic_bitset, 167
qpp::Bit_circuit, 134	storage_size_
qpp::Gates, 184	
save	qpp::Dynamic_bitset, 168
qpp, 101	storage_type
qpp::RandomDevices, 328	qpp::Dynamic_bitset, 160
saveMATLAB	subsys_
qpp, 101, 102	qpp::QEngine, 308
schatten	sum
qpp, 103	qpp, 108, 109
schmidtA	super2choi
	qpp, 109
qpp, 103	svals
schmidtB	qpp, 110
qpp, 104	svd
schmidtcoeffs	qpp, 110
qpp, 105	svdU
schmidtprobs	qpp, 111
qpp, 106	svdV
separator_	qpp, 111
qpp::internal::IOManipPointer, 202	syspermute
qpp::internal::IOManipRange, 205	qpp, 111, 112
set	
qpp::Dynamic_bitset, 166, 167	T
set_begin_	qpp::Gates, 185
qpp::QCircuit::iterator, 215	TFQ
set_dit	qpp, 112
qpp::QEngine, 304	qpp::QCircuit, 291, 292
set_end_	TOF
qpp::QCircuit::iterator, 215	qpp::Bit_circuit, 135
set_measured_	qpp::Gates, 185
qpp::QEngine, 306	target_
set psi	qpp::QCircuit::GateStep, 188
qpp::QEngine, 306	qpp::QCircuit::MeasureStep, 236
sigma	tic
qpp, 107	qpp::Timer, 348
Singleton	tics
qpp::internal::Singleton, 330, 331	qpp::Timer, 349
sinm	Timer
qpp, 107	qpp::Timer, 347
size	to_JSON
	qpp::IJSON, 192
qpp::Dynamic_bitset, 167	
spectralpowm	qpp::QCircuit, 293

	qpp::QEngine, 306	Υ		
to_st		•	qpp::Gates, 1	185
	qpp::Dynamic_bitset, 167	y0	qppo.a.co,	
to_v			qpp::States,	343
	qpp, 28	y1		
toc			qpp::States,	343
	qpp::Timer, 349			
trace		Z		
	qpp, 113		qpp::Gates, 1	185
traits	.h, 398	z0		
trans	pose		qpp::States,	343
	qpp, 113	z1		0.40
tsalli		Zd	qpp::States,	343
_	qpp, 114	Zū	ann::Gatos	100
Type		70r0	qpp::Gates, 1	103
	qpp::Codes, 138	zero	qpp::States,	330
type	1. 11.047		qppstates,	339
	qpp::make_void, 217			
type_				
	qpp::QCircuit::iterator::value_type_, 359			
types	s.h, 400			
unifo	rm			
	qpp, 115			
	900, 110			
v _				
	qpp::Dynamic_bitset, 168			
	e_type			
	qpp::Dynamic_bitset, 160			
	qpp::QCircuit::iterator, 213			
	e_type_			
	qpp::QCircuit::iterator::value_type_, 357, 358			
value	e_type_qc_			
	qpp::QCircuit::iterator::value_type_, 359			
var				
	qpp, 115			
	dic_vector_emplace			
varia	qpp::internal, 125			
	apptorrai, 120			
W				
	qpp::States, 342			
what				
	qpp::exception::Exception, 172			
what	_			
	qpp::exception::CustomException, 142			
wher	re_			
	qpp::exception::Exception, 173			
Χ				
	qpp::Bit_circuit, 135			
	qpp::Gates, 185			
x0				
	qpp::States, 342			
x1				
	qpp::States, 343			
	ntfrac			
	qpp, 115			
Xd				
	opp::Gates, 182			