Quantum++ v1.1

Generated by Doxygen 1.8.14

## **Contents**

1	Qua	ntum++																	1
2	Nam	nespace	space Index 3																
	2.1	Names	space List									 	 		 	 	 		 3
3	Hier	archica	l Index																5
	3.1	Class	Hierarchy									 	 		 	 	 		 5
4	Clas	s Index																	7
	4.1	Class	List									 	 		 	 	 		 7
5	File	Index																	11
	5.1	File Lis	st									 	 		 	 	 		 11
6	Nam	nespace	Docume	nta	tion														13
	6.1	qpp Na	amespace	Re	ferer	nce .						 	 		 		 		 13
		6.1.1	Detailed	De	scrip	tion						 	 		 	 	 		 26
		6.1.2	Typedef	Dod	cume	entati	on .					 	 		 	 	 		 26
			6.1.2.1	bi	igint							 	 		 	 	 		 26
			6.1.2.2	bı	ra .							 	 		 	 	 		 26
			6.1.2.3	CI	mat							 	 		 	 	 		 27
			6.1.2.4	c	plx .							 	 		 	 	 		 27
			6.1.2.5	dı	mat							 	 		 		 		 27
			6.1.2.6	dy	yn_c	ol_ve	ect .					 	 		 		 		 27
			6.1.2.7	dy	yn_m	nat .						 	 		 	 	 		 27
			6.1.2.8	d١	vn ro	ow v	ect					 	 		 	 	 		 28

ii CONTENTS

	6.1.2.9	idx	28
	6.1.2.10	ket	28
	6.1.2.11	to_void	28
6.1.3	Function	Documentation	28
	6.1.3.1	absm()	28
	6.1.3.2	abssq() [1/3]	29
	6.1.3.3	abssq() [2/3]	29
	6.1.3.4	abssq() [3/3]	30
	6.1.3.5	adjoint()	30
	6.1.3.6	anticomm()	30
	6.1.3.7	<b>apply()</b> [1/5]	31
	6.1.3.8	<b>apply()</b> [2/5]	31
	6.1.3.9	<b>apply()</b> [3/5]	32
	6.1.3.10	<b>apply()</b> [4/5]	32
	6.1.3.11	<b>apply()</b> [5/5]	33
	6.1.3.12	applyCTRL() [1/2]	33
	6.1.3.13	applyCTRL() [2/2]	34
	6.1.3.14	applyQFT()	35
	6.1.3.15	applyTFQ()	35
	6.1.3.16	avg()	36
	6.1.3.17	bloch2rho()	36
	6.1.3.18	choi2kraus()	37
	6.1.3.19	choi2super()	37
	6.1.3.20	comm()	38
	6.1.3.21	complement()	38
	6.1.3.22	compperm()	38
	6.1.3.23	concurrence()	40
	6.1.3.24	conjugate()	40
	6.1.3.25	contfrac2x()	41
	6.1.3.26	convergents() [1/2]	41

6.1.3.27	convergents() [2/2]	42
6.1.3.28	cor()	42
6.1.3.29	cosm()	43
6.1.3.30	cov()	43
6.1.3.31	cwise()	43
6.1.3.32	det()	44
6.1.3.33	dirsum() [1/4]	44
6.1.3.34	dirsum() [2/4]	45
6.1.3.35	dirsum() [3/4]	45
6.1.3.36	dirsum() [4/4]	46
6.1.3.37	dirsumpow()	46
6.1.3.38	disp() [1/5]	47
6.1.3.39	disp() [2/5]	47
6.1.3.40	disp() [3/5]	47
6.1.3.41	disp() [4/5]	48
6.1.3.42	disp() [5/5]	48
6.1.3.43	egcd()	49
6.1.3.44	eig()	49
6.1.3.45	entanglement() [1/2]	50
6.1.3.46	entanglement() [2/2]	50
6.1.3.47	entropy() [1/2]	51
6.1.3.48	entropy() [2/2]	51
6.1.3.49	evals()	52
6.1.3.50	evects()	52
6.1.3.51	expm()	52
6.1.3.52	factors()	53
6.1.3.53	funm()	53
6.1.3.54	gcd() [1/2]	54
6.1.3.55	gcd() [2/2]	54
6.1.3.56	gconcurrence()	55

iv CONTENTS

6.1.3.57	grams() [1/3]	55
6.1.3.58	grams() [2/3]	55
6.1.3.59	grams() [3/3]	56
6.1.3.60	heig()	56
6.1.3.61	hevals()	57
6.1.3.62	hevects()	57
6.1.3.63	inverse()	58
6.1.3.64	invperm()	58
6.1.3.65	ip() [1/2]	58
6.1.3.66	ip() [2/2]	59
6.1.3.67	isprime()	59
6.1.3.68	kraus2choi()	60
6.1.3.69	kraus2super()	60
6.1.3.70	kron() [1/4]	61
6.1.3.71	kron() [2/4]	61
6.1.3.72	kron() [3/4]	62
6.1.3.73	kron() [4/4]	62
6.1.3.74	kronpow()	62
6.1.3.75	lcm() [1/2]	63
6.1.3.76	lcm() [2/2]	63
6.1.3.77	load()	64
6.1.3.78	loadMATLAB() [1/2]	64
6.1.3.79	loadMATLAB() [2/2]	65
6.1.3.80	logdet()	66
6.1.3.81	logm()	66
6.1.3.82	lognegativity() [1/2]	67
6.1.3.83	lognegativity() [2/2]	67
6.1.3.84	marginalX()	67
6.1.3.85	marginalY()	69
6.1.3.86	measure() [1/9]	69

6.1.3.87 measure() [2/9]	70
6.1.3.88 measure() [3/9]	70
6.1.3.89 measure() [4/9]	70
6.1.3.90 measure() [5/9]	'1
6.1.3.91 measure() [6/9]	2
6.1.3.92 measure() [7/9]	72
6.1.3.93 measure() [8/9]	73
6.1.3.94 measure() [9/9]	74
6.1.3.95 measure_seq() [1/2]	<sup>7</sup> 4
6.1.3.96 measure_seq() [2/2]	75
6.1.3.97 mket() [1/2]	75
6.1.3.98 mket() [2/2]	76
6.1.3.99 modinv()	76
6.1.3.100 modmul()	7
6.1.3.101 modpow()	7
6.1.3.102 mprj() [1/2]	78
6.1.3.103 mprj() [2/2]	79
6.1.3.104 multiidx2n()	79
6.1.3.105 n2multiidx()	30
6.1.3.106 negativity() [1/2]	30
6.1.3.107 negativity() [2/2]	30
6.1.3.108 norm()	31
6.1.3.109 normalize()	31
6.1.3.110 omega()	32
6.1.3.111 operator""""_i()	32
6.1.3.112 powm()	32
6.1.3.113 prj()	33
6.1.3.114 prod() [1/3]	33
6.1.3.115 prod() [2/3]	34
6.1.3.116 prod() [3/3]	34

vi

6.1.3.117 ptrace() [1/2]
6.1.3.118 ptrace() [2/2]
6.1.3.119 ptrace1() [1/2]
6.1.3.120 ptrace1() [2/2]
6.1.3.121 ptrace2() [1/2]
6.1.3.122 ptrace2() [2/2]
6.1.3.123 ptranspose() [1/2]
6.1.3.124 ptranspose() [2/2]
6.1.3.125 QFT()
6.1.3.126 qmutualinfo() [1/2]
6.1.3.127 qmutualinfo() [2/2]
6.1.3.128 rand() [1/5] 90
6.1.3.129 rand() [2/5] 90
6.1.3.130 rand() [3/5] 91
6.1.3.131 rand() [4/5] 91
6.1.3.132 rand() [5/5]
6.1.3.133 randH()
6.1.3.134 randidx()
6.1.3.135 randket()
6.1.3.136 randkraus()
6.1.3.137 randn() [1/4] 94
6.1.3.138 randn() [2/4] 94
6.1.3.139 randn() [3/4]
6.1.3.140 randn() [4/4]
6.1.3.141 randperm()
6.1.3.142 randprime()
6.1.3.143 randprob()
6.1.3.144 randrho()
6.1.3.145 randU()
6.1.3.146 randV()

CONTENTS vii

6.1.3.147 renyi() [1/2]
6.1.3.148 renyi() [2/2]
6.1.3.149 reshape()
6.1.3.150 rho2bloch()
6.1.3.151 rho2pure()
6.1.3.152 save()
6.1.3.153 saveMATLAB() [1/2]
6.1.3.154 saveMATLAB() [2/2]
6.1.3.155 schatten()
6.1.3.156 schmidtA() [1/2]
6.1.3.157 schmidtA() [2/2]
6.1.3.158 schmidtB() [1/2]
6.1.3.159 schmidtB() [2/2]
6.1.3.160 schmidtcoeffs() [1/2]
6.1.3.161 schmidtcoeffs() [2/2]
6.1.3.162 schmidtprobs() [1/2]
6.1.3.163 schmidtprobs() [2/2]
6.1.3.164 sigma()
6.1.3.165 sinm()
6.1.3.166 spectralpowm()
6.1.3.167 sqrtm()
6.1.3.168 sum() [1/3]
6.1.3.169 sum() [2/3]
6.1.3.170 sum() [3/3]
6.1.3.171 super2choi()
6.1.3.172 svals()
6.1.3.173 svd()
6.1.3.174 svdU()
6.1.3.175 svdV()
6.1.3.176 syspermute() [1/2]

viii CONTENTS

		6.1.3.177	7 syspermute() [2/2]	112
		6.1.3.178	8 TFQ()	112
		6.1.3.179	9 trace()	113
		6.1.3.180	0 transpose()	113
		6.1.3.181	1 tsallis() [1/2]	113
		6.1.3.182	2 tsallis() [2/2]	114
		6.1.3.183	3 uniform()	114
		6.1.3.184	4 var()	115
		6.1.3.185	5 x2contfrac()	115
	6.1.4	Variable	Documentation	116
		6.1.4.1	chop	116
		6.1.4.2	ee	116
		6.1.4.3	eps	116
		6.1.4.4	idx_infty	116
		6.1.4.5	infty	116
		6.1.4.6	maxn	117
		6.1.4.7	pi	117
6.2	qpp::ex	ception N	lamespace Reference	117
	6.2.1	Detailed	Description	118
6.3	qpp::ex	perimenta	al Namespace Reference	119
	6.3.1	Detailed	Description	119
6.4	qpp::in	ternal Nan	mespace Reference	119
	6.4.1	Detailed	Description	120
	6.4.2	Function	Documentation	120
		6.4.2.1	check_cvector()	120
		6.4.2.2	check_dims()	120
		6.4.2.3	check_dims_match_cvect()	121
		6.4.2.4	check_dims_match_mat()	121
		6.4.2.5	check_dims_match_rvect()	121
		6.4.2.6	check_eq_dims()	121

		6.4.2.7	check_matching_sizes()	21
		6.4.2.8	check_no_duplicates()	21
		6.4.2.9	check_nonzero_size()	22
		6.4.2.10	check_perm()	22
		6.4.2.11	check_qubit_cvector()	22
		6.4.2.12	check_qubit_matrix()	22
		6.4.2.13	check_qubit_rvector()	22
		6.4.2.14	check_qubit_vector()	22
		6.4.2.15	check_rvector()	23
		6.4.2.16	check_square_mat()	23
		6.4.2.17	check_subsys_match_dims()	23
		6.4.2.18	check_vector()	23
		6.4.2.19	dirsum2()	23
		6.4.2.20	get_dim_subsys()	23
		6.4.2.21	get_num_subsys()	24
		6.4.2.22	kron2()	24
		6.4.2.23	multiidx2n()	24
		6.4.2.24	n2multiidx()	24
		6.4.2.25	variadic_vector_emplace() [1/2]	24
		6.4.2.26	variadic_vector_emplace() [2/2]	24
6.5	qpp::lit	erals Nam	espace Reference	25
	6.5.1	Function	Documentation	25
		6.5.1.1	operator""""_bra()	25
		6.5.1.2	operator""""_i()	25
		6.5.1.3	operator"""" _ket()	26
		6.5.1.4	operator"""" _prj()	26

7	Clas	s Docu	mentation	129
	7.1	qpp::Bi	t_circuit Class Reference	129
		7.1.1	Detailed Description	131
		7.1.2	Constructor & Destructor Documentation	131
			7.1.2.1 Bit_circuit()	131
		7.1.3	Member Function Documentation	131
			7.1.3.1 CNOT()	131
			7.1.3.2 Dynamic_bitset()	132
			7.1.3.3 FRED()	132
			7.1.3.4 NOT()	132
			7.1.3.5 reset()	133
			7.1.3.6 SWAP()	133
			7.1.3.7 TOF()	133
			7.1.3.8 X()	134
		7.1.4	Member Data Documentation	134
			7.1.4.1 gate_count	134
	7.2	qpp::C	odes Class Reference	134
		7.2.1	Detailed Description	135
		7.2.2	Member Enumeration Documentation	135
			7.2.2.1 Type	136
		7.2.3	Constructor & Destructor Documentation	136
			7.2.3.1 Codes()	136
			7.2.3.2 ~Codes()	136
		7.2.4	Member Function Documentation	136
			7.2.4.1 codeword()	136
		7.2.5	Friends And Related Function Documentation	137
			7.2.5.1 internal::Singleton < const Codes >	137
	7.3	qpp::ex	cception::CustomException Class Reference	137
		7.3.1	Detailed Description	138
		7.3.2	Constructor & Destructor Documentation	138

CONTENTS xi

		7.3.2.1	CustomException()	. 139
	7.3.3	Member F	Function Documentation	. 139
		7.3.3.1	type_description()	. 139
	7.3.4	Member [	Data Documentation	. 139
		7.3.4.1	what	. 139
7.4	qpp::ex	xception::D	imsInvalid Class Reference	. 140
	7.4.1	Detailed [	Description	. 141
	7.4.2	Member F	Function Documentation	. 141
		7.4.2.1	Exception()	. 141
		7.4.2.2	type_description()	. 141
7.5	qpp::ex	xception::D	imsMismatchCvector Class Reference	. 142
	7.5.1	Detailed [	Description	. 143
	7.5.2	Member F	Function Documentation	. 143
		7.5.2.1	Exception()	. 143
		7.5.2.2	type_description()	. 143
7.6	qpp::ex	xception::D	imsMismatchMatrix Class Reference	. 144
	7.6.1	Detailed [	Description	. 145
	7.6.2	Member F	Function Documentation	. 145
		7.6.2.1	Exception()	. 145
		7.6.2.2	type_description()	. 145
7.7	qpp::ex	xception::D	imsMismatchRvector Class Reference	. 146
	7.7.1	Detailed [	Description	. 147
	7.7.2	Member F	Function Documentation	. 147
		7.7.2.1	Exception()	. 147
		7.7.2.2	type_description()	. 147
7.8	qpp::ex	xception::D	imsMismatchVector Class Reference	. 148
	7.8.1	Detailed [	Description	. 149
	7.8.2	Member F	Function Documentation	. 149
		7.8.2.1	Exception()	. 149
		7.8.2.2	type_description()	. 149

xii CONTENTS

7.9	qpp::ex	cception::DimsNotEqual Class Reference
	7.9.1	Detailed Description
	7.9.2	Member Function Documentation
		7.9.2.1 Exception()
		7.9.2.2 type_description()
7.10	qpp::in	ternal::Display_Impl_ Struct Reference
	7.10.1	Member Function Documentation
		7.10.1.1 display_impl_()
7.11	qpp::ex	cception::Duplicates Class Reference
	7.11.1	Detailed Description
	7.11.2	Member Function Documentation
		7.11.2.1 Exception()
		7.11.2.2 type_description()
7.12	qpp::D	ynamic_bitset Class Reference
	7.12.1	Detailed Description
	7.12.2	Member Typedef Documentation
		7.12.2.1 storage_type
		7.12.2.2 value_type
	7.12.3	Constructor & Destructor Documentation
		7.12.3.1 Dynamic_bitset()
		7.12.3.2 ~Dynamic_bitset()
	7.12.4	Member Function Documentation
		7.12.4.1 all()
		7.12.4.2 any()
		7.12.4.3 count()
		7.12.4.4 data()
		7.12.4.5 display()
		7.12.4.6 flip() [1/2]
		7.12.4.7 flip() [2/2]
		7.12.4.8 get()

CONTENTS xiii

		7.12.4.9 index_()	60
		7.12.4.10 none()	61
		7.12.4.11 offset_()	61
		7.12.4.12 operator"!=()	61
		7.12.4.13 operator-()	62
		7.12.4.14 operator==()	62
		7.12.4.15 rand() [1/2]	62
		7.12.4.16 rand() [2/2]	63
		7.12.4.17 reset() [1/2]	63
		7.12.4.18 reset() [2/2]	63
		7.12.4.19 set() [1/2]	64
		7.12.4.20 set() [2/2]	64
		7.12.4.21 size()	64
		7.12.4.22 storage_size()	64
		7.12.4.23 to_string()	65
	7.12.5	Member Data Documentation	65
		7.12.5.1 N	65
		7.12.5.2 storage_size	65
		7.12.5.3 v	66
7.13	qpp::ex	cception::Exception Class Reference	66
	7.13.1	Detailed Description	68
	7.13.2	Constructor & Destructor Documentation	69
		7.13.2.1 Exception()	69
	7.13.3	Member Function Documentation	69
		7.13.3.1 type_description()	69
		7.13.3.2 what()	70
	7.13.4	Member Data Documentation	70
		7.13.4.1 msg	70
		7.13.4.2 where	70
7.14	qpp::Bi	it_circuit::Gate_count Struct Reference	70

xiv CONTENTS

	7.14.1	Member Data Documentation
		7.14.1.1 CNOT
		7.14.1.2 FRED
		7.14.1.3 NOT
		7.14.1.4 SWAP
		7.14.1.5 TOF
		7.14.1.6 X
7.15	qpp::Ga	ates Class Reference
	7.15.1	Detailed Description
	7.15.2	Constructor & Destructor Documentation
		7.15.2.1 Gates()
		7.15.2.2 ~Gates()
	7.15.3	Member Function Documentation
		7.15.3.1 CTRL()
		7.15.3.2 expandout() [1/3]
		7.15.3.3 expandout() [2/3]
		7.15.3.4 expandout() [3/3]
		7.15.3.5 Fd()
		7.15.3.6 get_name()
		7.15.3.7 ld()
		7.15.3.8 MODMUL()
		7.15.3.9 Rn()
		7.15.3.10 RX()
		7.15.3.11 RY()
		7.15.3.12 RZ()
		7.15.3.13 SWAPd()
		7.15.3.14 Xd()
		7.15.3.15 Zd()
	7.15.4	Friends And Related Function Documentation
		7.15.4.1 internal::Singleton < const Gates >

CONTENTS xv

7	'.15.5	Member Data Documentation
		7.15.5.1 CNOT
		7.15.5.2 CNOTba
		7.15.5.3 CZ
		7.15.5.4 FRED
		7.15.5.5 H
		7.15.5.6 ld2
		7.15.5.7 S
		7.15.5.8 SWAP
		7.15.5.9 T
		7.15.5.10 TOF
		7.15.5.11 X
		7.15.5.12 Y
		7.15.5.13 Z
7.16 q	pp::Q0	Circuit::GateStep Struct Reference
7	'.16.1	Detailed Description
7	7.16.2	Constructor & Destructor Documentation
		7.16.2.1 GateStep() [1/2]
		7.16.2.2 GateStep() [2/2]
7	7.16.3	Member Data Documentation
		7.16.3.1 ctrl
		7.16.3.2 gate
		7.16.3.3 gate_type
		7.16.3.4 name
		7.16.3.5 target
7.17 q	pp::ID	isplay Class Reference
7	7.17.1	Detailed Description
7	7.17.2	Constructor & Destructor Documentation
		7.17.2.1   IDisplay() [1/3]
		7.17.2.2 IDisplay() [2/3]

xvi CONTENTS

		7.17.2.3   IDisplay() [3/3]
		7.17.2.4 ~IDisplay()
	7.17.3	Member Function Documentation
		7.17.3.1 display()
		7.17.3.2 operator=() [1/2]
		7.17.3.3 operator=() [2/2]
	7.17.4	Friends And Related Function Documentation
		7.17.4.1 operator<<
7.18	qpp::lJ	SON Class Reference
	7.18.1	Detailed Description
	7.18.2	Constructor & Destructor Documentation
		7.18.2.1 IJSON() [1/3]
		7.18.2.2 IJSON() [2/3]
		7.18.2.3 IJSON() [3/3]
		7.18.2.4 ~IJSON()
	7.18.3	Member Function Documentation
		7.18.3.1 operator=() [1/2]
		7.18.3.2 operator=() [2/2]
		7.18.3.3 to_JSON()
7.19	qpp::ln	it Class Reference
	7.19.1	Detailed Description
	7.19.2	Constructor & Destructor Documentation
		7.19.2.1 Init()
		7.19.2.2 ~Init()
	7.19.3	Friends And Related Function Documentation
		7.19.3.1 internal::Singleton < const Init >
7.20	qpp::ex	cception::InvalidIterator Class Reference
	7.20.1	Detailed Description
	7.20.2	Member Function Documentation
		7.20.2.1 Exception()

CONTENTS xvii

		7.20.2.2 type_description()	197
7.21	qpp::int	ternal::IOManipEigen Class Reference	197
	7.21.1	Constructor & Destructor Documentation	199
		7.21.1.1 IOManipEigen() [1/2]	199
		7.21.1.2 IOManipEigen() [2/2]	199
	7.21.2	Member Function Documentation	199
		7.21.2.1 display()	199
	7.21.3	Member Data Documentation	199
		7.21.3.1 A	199
		7.21.3.2 chop	200
7.22	qpp::int	ternal::IOManipPointer< PointerType > Class Template Reference	200
	7.22.1	Constructor & Destructor Documentation	201
		7.22.1.1 IOManipPointer() [1/2]	201
		7.22.1.2 IOManipPointer() [2/2]	201
	7.22.2	Member Function Documentation	201
		7.22.2.1 display()	202
		7.22.2.2 operator=()	202
	7.22.3	Member Data Documentation	202
		7.22.3.1 end	202
		7.22.3.2 N	202
		7.22.3.3 p	202
		7.22.3.4 separator	203
		7.22.3.5 start	203
7.23	qpp::int	ternal::IOManipRange < InputIterator > Class Template Reference	203
	7.23.1	Constructor & Destructor Documentation	204
		7.23.1.1 IOManipRange() [1/2]	205
		7.23.1.2 IOManipRange() [2/2]	205
	7.23.2	Member Function Documentation	205
		7.23.2.1 display()	205
		7.23.2.2 operator=()	205

xviii CONTENTS

	7.23.3	Member Data Documentation	05
		7.23.3.1 end	06
		7.23.3.2 first	06
		7.23.3.3 last	06
		7.23.3.4 separator	06
		7.23.3.5 start	06
7.24	qpp::is_	_complex< T > Struct Template Reference	07
	7.24.1	Detailed Description	07
7.25	qpp::is_	_complex< std::complex< T > > Struct Template Reference	80
	7.25.1	Detailed Description	80
7.26	qpp::is_	_iterable < T, typename > Struct Template Reference	09
	7.26.1	Detailed Description	09
7.27		_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T d()), decltype(*(std::declval < T >().begin())) > Struct Template Reference	10
	7.27.1	Detailed Description	11
7.28	qpp::is_	_matrix_expression< Derived > Struct Template Reference	11
	7.28.1	Detailed Description	11
7.29	qpp::Q0	Circuit::iterator Class Reference	12
	7.29.1	Detailed Description	13
	7.29.2	Member Typedef Documentation	13
		7.29.2.1 difference_type	13
		7.29.2.2 iterator_category	13
		7.29.2.3 pointer	14
		7.29.2.4 reference	14
		7.29.2.5 value_type	14
	7.29.3	Constructor & Destructor Documentation	14
		7.29.3.1 iterator() [1/2]	14
		7.29.3.2 iterator() [2/2]	14
	7.29.4	Member Function Documentation	14
		7.29.4.1 operator"!=()	14
		7.29.4.2 operator*()	15

CONTENTS xix

		7.29.4.3 operator++() [1/2]	15
		7.29.4.4 operator++() [2/2]	15
		7.29.4.5 operator=()	16
		7.29.4.6 operator==()	16
		7.29.4.7 set_begin_()	16
		7.29.4.8 set_end_()	16
	7.29.5	Member Data Documentation	17
		7.29.5.1 elem	17
		7.29.5.2 qcd	17
7.30	qpp::ma	ake_void< Ts > Struct Template Reference	17
	7.30.1	Detailed Description	17
	7.30.2	Member Typedef Documentation	18
		7.30.2.1 type	18
7.31	qpp::ex	cception::MatrixMismatchSubsys Class Reference	18
	7.31.1	Detailed Description	19
	7.31.2	Member Function Documentation	19
		7.31.2.1 Exception()	19
		7.31.2.2 type_description()	20
7.32	qpp::ex	cception::MatrixNotCvector Class Reference	20
	7.32.1	Detailed Description	21
	7.32.2	Member Function Documentation	21
		7.32.2.1 Exception()	21
		7.32.2.2 type_description()	22
7.33	qpp::ex	cception::MatrixNotRvector Class Reference	22
	7.33.1	Detailed Description	23
	7.33.2	Member Function Documentation	23
		7.33.2.1 Exception()	23
		7.33.2.2 type_description()	24
7.34	qpp::ex	cception::MatrixNotSquare Class Reference	24
	7.34.1	Detailed Description	25

	7.34.2	Member Function Documentation	225
		7.34.2.1 Exception()	225
		7.34.2.2 type_description()	226
7.35	qpp::ex	xception::MatrixNotSquareNorCvector Class Reference	226
	7.35.1	Detailed Description	227
	7.35.2	Member Function Documentation	227
		7.35.2.1 Exception()	227
		7.35.2.2 type_description()	228
7.36	qpp::ex	xception::MatrixNotSquareNorRvector Class Reference	228
	7.36.1	Detailed Description	229
	7.36.2	Member Function Documentation	229
		7.36.2.1 Exception()	229
		7.36.2.2 type_description()	230
7.37	qpp::ex	cception::MatrixNotSquareNorVector Class Reference	230
	7.37.1	Detailed Description	231
	7.37.2	Member Function Documentation	231
		7.37.2.1 Exception()	231
		7.37.2.2 type_description()	232
7.38	qpp::ex	cception::MatrixNotVector Class Reference	232
	7.38.1	Detailed Description	233
	7.38.2	Member Function Documentation	233
		7.38.2.1 Exception()	233
		7.38.2.2 type_description()	234
7.39	qpp::Q	Circuit::MeasureStep Struct Reference	234
	7.39.1	Detailed Description	235
	7.39.2	Constructor & Destructor Documentation	235
		7.39.2.1 MeasureStep() [1/2]	235
		7.39.2.2 MeasureStep() [2/2]	235
	7.39.3	Member Data Documentation	236
		7.39.3.1 c_reg	236

CONTENTS xxi

		7.39.3.2 mats	23
		7.39.3.3 measurement_type	23
		7.39.3.4 name	23
		7.39.3.5 target	23
7.40	qpp::ex	ception::NoCodeword Class Reference	23
	7.40.1	Detailed Description	23
	7.40.2	Member Function Documentation	23
		7.40.2.1 Exception()	23
		7.40.2.2 type_description()	23
7.41	qpp::No	iseBase< T > Class Template Reference	23
	7.41.1	Detailed Description	24
	7.41.2	Member Typedef Documentation	24
		7.41.2.1 noise_type	24
	7.41.3	Constructor & Destructor Documentation	24
		7.41.3.1 NoiseBase() [1/2]	24
		7.41.3.2 NoiseBase() [2/2]	24
		7.41.3.3 ~NoiseBase()	24
	7.41.4	Member Function Documentation	24
		7.41.4.1 compute_probs_()	24
		7.41.4.2 compute_state_()	24
		7.41.4.3 get_d()	24
		7.41.4.4 get_Ks()	24
		7.41.4.5 get_last_idx()	24
		7.41.4.6 get_last_K()	24
		7.41.4.7 get_last_p()	24
		7.41.4.8 get_probs()	24
		7.41.4.9 operator()() [1/2]	24
		7.41.4.10 operator()() [2/2]	24
	7.41.5	Member Data Documentation	24
		7.41.5.1 d	24

xxii CONTENTS

		7.41.5.2	ge	enerate	ed					 	 	 	 	 	 	 245
		7.41.5.3	i_							 	 	 	 	 	 	 246
		7.41.5.4	K	<b>s</b>						 	 	 	 	 	 	 246
		7.41.5.5	pr	obs_						 	 	 	 	 	 	 246
7.42	qpp::No	oiseType C	Clas	ss Refe	erenc	ce .				 	 	 	 	 	 	 246
	7.42.1	Detailed I	De	scriptio	on .					 	 	 	 	 	 	 246
7.43	qpp::ex	ception::N	VotE	3ipartit	te Cla	ass F	Refere	ence		 	 	 	 	 	 	 247
	7.43.1	Detailed I	De	scriptio	on .					 	 	 	 	 	 	 248
	7.43.2	Member I	Fur	nction	Docu	umer	ntation	n .		 	 	 	 	 	 	 248
		7.43.2.1	E	xceptio	on() .					 	 	 	 	 	 	 248
		7.43.2.2	ty	pe_de	scrip	otion(	()			 	 	 	 	 	 	 248
7.44	qpp::ex	ception::N	Votl	mplem	nente	ed Cla	ass P	Refere	ence	 	 	 	 	 	 	 249
	7.44.1	Detailed I	De	scriptio	on .					 	 	 	 	 	 	 250
	7.44.2	Member I	Fur	nction	Docu	umer	ntation	n .		 	 	 	 	 	 	 250
		7.44.2.1	E:	xceptio	on() .					 	 	 	 	 	 	 250
		7.44.2.2	ty	pe_de	scrip	otion(	()			 	 	 	 	 	 	 250
7.45	qpp::ex	ception::N	Vot(	QubitC	vecto	or Cl	ass F	Refere	ence	 	 	 	 	 	 	 251
	7.45.1	Detailed I	De	scriptio	on .					 	 	 	 	 	 	 252
	7.45.2	Member I	Fur	nction	Docu	umer	ntation	n .		 	 	 	 	 	 	 252
		7.45.2.1	E:	xceptio	on() .					 	 	 	 	 	 	 252
		7.45.2.2	ty	pe_de	scrip	otion(	()			 	 	 	 	 	 	 252
7.46	qpp::ex	ception::N	Vot(	QubitM	1atrix	Clas	ss Re	eferer	nce .	 	 	 	 	 	 	 253
	7.46.1	Detailed I	De	scriptio	on .					 	 	 	 	 	 	 254
	7.46.2	Member I	Fur	nction	Docu	umer	ntatio	n .		 	 	 	 	 	 	 254
		7.46.2.1	E	xceptio	on() .					 	 	 	 	 	 	 254
		7.46.2.2	ty	pe_de	scrip	otion(	()			 	 	 	 	 	 	 254
7.47	qpp::ex	ception::N	Vot(	QubitR	lvecto	or Cl	ass F	Refere	ence	 	 	 	 	 	 	 255
	7.47.1	Detailed I	De	scriptio	on .					 	 	 	 	 	 	 256
	7.47.2	Member I	Fur	nction	Docu	umer	ntatio	n .		 	 	 	 	 	 	 256
		7.47.2.1	E	xceptic	on() .					 	 	 	 	 	 	 256

CONTENTS xxiii

		7.47.2.2	type_description()	 	 	 	 	256
7.48	qpp::ex	ception::N	tQubitSubsys Class Reference	 	 	 	 	257
	7.48.1	Detailed [	escription	 	 	 	 	258
	7.48.2	Member F	unction Documentation	 	 	 	 	258
		7.48.2.1	Exception()	 	 	 	 	258
		7.48.2.2	type_description()	 	 	 	 	258
7.49	qpp::ex	ception::N	tQubitVector Class Reference	 	 	 	 	259
	7.49.1	Detailed [	escription	 	 	 	 	260
	7.49.2	Member F	unction Documentation	 	 	 	 	260
		7.49.2.1	Exception()	 	 	 	 	260
		7.49.2.2	type_description()	 	 	 	 	260
7.50	qpp::ex	ception::O	utOfRange Class Reference	 	 	 	 	261
	7.50.1	Detailed [	escription	 	 	 	 	262
	7.50.2	Member F	unction Documentation	 	 	 	 	262
		7.50.2.1	Exception()	 	 	 	 	262
		7.50.2.2	type_description()	 	 	 	 	262
7.51	qpp::ex	ception::Po	rmInvalid Class Reference	 	 	 	 	263
	7.51.1	Detailed [	escription	 	 	 	 	264
	7.51.2	Member F	unction Documentation	 	 	 	 	264
		7.51.2.1	Exception()	 	 	 	 	264
		7.51.2.2	type_description()	 	 	 	 	264
7.52	qpp::ex	ception::Pe	rmMismatchDims Class Reference	 	 	 	 	265
	7.52.1	Detailed [	escription	 	 	 	 	266
	7.52.2	Member F	unction Documentation	 	 	 	 	266
		7.52.2.1	Exception()	 	 	 	 	266
		7.52.2.2	type_description()	 	 	 	 	266
7.53	qpp::Q	Circuit Clas	s Reference	 	 	 	 	267
	7.53.1	Detailed [	escription	 	 	 	 	271
	7.53.2	Member 7	pedef Documentation	 	 	 	 	271
		7.53.2.1	const_iterator	 	 	 	 	271

xxiv CONTENTS

7.53.3	Member Enume	ration Docu	mentati	on	 	 	 	 	 271
	7.53.3.1 Gate1	ype			 	 	 	 	 271
	7.53.3.2 Meas	ureType			 	 	 	 	 272
	7.53.3.3 StepT	iype			 	 	 	 	 272
7.53.4	Constructor & D	estructor Do	ocumen	tation .	 	 	 	 	 273
	7.53.4.1 QCirc	uit()			 	 	 	 	 273
	7.53.4.2 ∼QCi	rcuit()			 	 	 	 	 273
7.53.5	Member Function	n Documen	tation		 	 	 	 	 273
	7.53.5.1 begin	() [1/2] .			 	 	 	 	 274
	7.53.5.2 begin	() [2/2] .			 	 	 	 	 274
	7.53.5.3 cbegi	n()			 	 	 	 	 274
	7.53.5.4 cCTR	<b>L()</b> [1/4] .			 	 	 	 	 274
	7.53.5.5 cCTR	<b>L()</b> [2/4] .			 	 	 	 	 275
	7.53.5.6 cCTR	<b>L()</b> [3/4] .			 	 	 	 	 275
	7.53.5.7 cCTR	<b>L()</b> [4/4] .			 	 	 	 	 276
	7.53.5.8 cCTR	L_custom()			 	 	 	 	 276
	7.53.5.9 cend(	)			 	 	 	 	 277
	7.53.5.10 CTRL	.() [1/4] .			 	 	 	 	 277
	7.53.5.11 CTRL	.() [2/4] .			 	 	 	 	 277
	7.53.5.12 CTRL	.() [3/4] .			 	 	 	 	 278
	7.53.5.13 CTRL	.() [4/4] .			 	 	 	 	 278
	7.53.5.14 CTRL	_custom()			 	 	 	 	 279
	7.53.5.15 displa	y()			 	 	 	 	 279
	7.53.5.16 end()	[1/2]			 	 	 	 	 280
	7.53.5.17 end()	[2/2]			 	 	 	 	 280
	7.53.5.18 gate()	[1/3]			 	 	 	 	 280
	7.53.5.19 gate()	[2/3]			 	 	 	 	 280
	7.53.5.20 gate()	[3/3]			 	 	 	 	 281
	7.53.5.21 gate_	custom() .			 	 	 	 	 281
	7.53.5.22 gate_	fan() [1/3]			 	 	 	 	 282

CONTENTS xxv

	7.53.5.23 gate_fan() [2/3]	32
	7.53.5.24 gate_fan() [3/3]	33
	7.53.5.25 get_d()	33
	7.53.5.26 get_gate_count() [1/2]	33
	7.53.5.27 get_gate_count() [2/2]	3
	7.53.5.28 get_gate_depth() [1/2]	34
	7.53.5.29 get_gate_depth() [2/2] 28	34
	7.53.5.30 get_gates_()	34
	7.53.5.31 get_measured() [1/2]	35
	7.53.5.32 get_measured() [2/2]	35
	7.53.5.33 get_measurement_count() [1/2]	35
	7.53.5.34 get_measurement_count() [2/2]	35
	7.53.5.35 get_measurements_()	36
	7.53.5.36 get_name()	36
	7.53.5.37 get_nc()	36
	7.53.5.38 get_non_measured()	37
	7.53.5.39 get_nq()	37
	7.53.5.40 get_step_count()	37
	7.53.5.41 measureV() [1/2]	37
	7.53.5.42 measureV() [2/2]	38
	7.53.5.43 measureZ()	38
	7.53.5.44 QFT()	39
	7.53.5.45 TFQ()	39
	7.53.5.46 to_JSON()	39
7.53.6	Friends And Related Function Documentation	<b>)</b> 0
	7.53.6.1 operator << [1/4]	<del>)</del> 0
	7.53.6.2 operator << [2/4]	<del>)</del> 0
	7.53.6.3 operator << [3/4]	<b>)</b> 1
	7.53.6.4 operator << [4/4]	<b>)</b> 1
	7.53.6.5 QEngine	1

xxvi CONTENTS

7.5	53.7	Member D	ata Docum	entation	١		 	 	 	 	 	292
		7.53.7.1	count				 	 	 	 	 	292
		7.53.7.2	d				 	 	 	 	 	292
		7.53.7.3	depth				 	 	 	 	 	292
		7.53.7.4	gates				 	 	 	 	 	292
		7.53.7.5	measured_				 	 	 	 	 	292
		7.53.7.6	measurem	ent_cou	nt		 	 	 	 	 	293
		7.53.7.7	measurem	ents			 	 	 	 	 	293
		7.53.7.8	name				 	 	 	 	 	293
		7.53.7.9	nc				 	 	 	 	 	293
		7.53.7.10	nq				 	 	 	 	 	293
		7.53.7.11	step_types				 	 	 	 	 	293
7.54 qp	p::QE	Engine Clas	ss Referenc	е			 	 	 	 	 	294
7.5	54.1	Detailed D	escription				 	 	 	 	 	296
7.5	54.2	Constructo	or & Destru	ctor Doc	cument	ation .	 	 	 	 	 	296
		7.54.2.1	QEngine()	[1/2] .			 	 	 	 	 	296
		7.54.2.2	QEngine()	[2/2] .			 	 	 	 	 	296
		7.54.2.3	$\sim$ QEngine	()			 	 	 	 	 	297
7.5	54.3	Member F	unction Do	cumenta	ation		 	 	 	 	 	297
		7.54.3.1	display() .				 	 	 	 	 	297
		7.54.3.2	execute() [	1/2] .			 	 	 	 	 	297
		7.54.3.3	execute() [	2/2] .			 	 	 	 	 	297
		7.54.3.4	get_circuit(	)			 	 	 	 	 	298
		7.54.3.5	get_dit() .				 	 	 	 	 	298
		7.54.3.6	get_dits() .				 	 	 	 	 	298
		7.54.3.7	get_measu	red() [1	./2] .		 	 	 	 	 	299
		7.54.3.8	get_measu	<b>red()</b> [2	2/2].		 	 	 	 	 	299
		7.54.3.9	get_not_m	easured	()		 	 	 	 	 	299
		7.54.3.10	get_probs(	)			 	 	 	 	 	299
		7.54.3.11	get_psi() .				 	 	 	 	 	300

CONTENTS xxvii

		7.54.3.12 get_ref_psi()	300
		7.54.3.13 get_relative_pos_()	300
		7.54.3.14 reset()	300
		7.54.3.15 set_dit()	301
		7.54.3.16 set_measured_()	301
		7.54.3.17 to_JSON()	301
	7.54.4	Member Data Documentation	302
		7.54.4.1 dits	302
		7.54.4.2 probs	302
		7.54.4.3 psi	302
		7.54.4.4 qcd	302
		7.54.4.5 subsys	302
7.55	qpp::Qı	ubitAmplitudeDampingNoise Class Reference	303
	7.55.1	Detailed Description	304
	7.55.2	Constructor & Destructor Documentation	304
		7.55.2.1 QubitAmplitudeDampingNoise()	304
7.56	qpp::Qı	ubitBitFlipNoise Class Reference	304
	7.56.1	Detailed Description	305
	7.56.2	Constructor & Destructor Documentation	305
		7.56.2.1 QubitBitFlipNoise()	305
7.57	qpp::Qı	ubitBitPhaseFlipNoise Class Reference	306
	7.57.1	Detailed Description	307
	7.57.2	Constructor & Destructor Documentation	307
		7.57.2.1 QubitBitPhaseFlipNoise()	307
7.58	qpp::Qı	ubitDepolarizingNoise Class Reference	307
	7.58.1	Detailed Description	308
	7.58.2	Constructor & Destructor Documentation	308
		7.58.2.1 QubitDepolarizingNoise()	308
7.59	qpp::Qı	ubitPhaseDampingNoise Class Reference	309
	7.59.1	Detailed Description	310

xxviii CONTENTS

		7.59.2	Constructor & Destructor Documentation	310
			7.59.2.1 QubitPhaseDampingNoise()	310
7	.60	qpp::Qı	ubitPhaseFlipNoise Class Reference	310
		7.60.1	Detailed Description	311
		7.60.2	Constructor & Destructor Documentation	311
			7.60.2.1 QubitPhaseFlipNoise()	311
7	'.61	qpp::ex	cception::QuditAlreadyMeasured Class Reference	312
		7.61.1	Detailed Description	313
		7.61.2	Member Function Documentation	313
			7.61.2.1 Exception()	313
			7.61.2.2 type_description()	314
7	.62	qpp::Qı	uditDepolarizingNoise Class Reference	314
		7.62.1	Detailed Description	315
		7.62.2	Constructor & Destructor Documentation	315
			7.62.2.1 QuditDepolarizingNoise()	315
		7.62.3	Member Function Documentation	316
			7.62.3.1 fill_Ks_()	316
			7.62.3.2 fill_probs_()	316
7	.63	qpp::Ra	andomDevices Class Reference	317
		7.63.1	Detailed Description	318
		7.63.2	Constructor & Destructor Documentation	318
			7.63.2.1 RandomDevices()	318
			7.63.2.2 ~RandomDevices()	319
		7.63.3	Member Function Documentation	319
			7.63.3.1 get_prng()	319
			7.63.3.2 load()	319
			7.63.3.3 save()	319
		7.63.4	Friends And Related Function Documentation	320
			7.63.4.1 internal::Singleton < RandomDevices >	320
		7.63.5	Member Data Documentation	320

CONTENTS xxix

		7.63.5.1 prng	20
		7.63.5.2 rd	20
7.64	qpp::int	ernal::Singleton < T > Class Template Reference	20
	7.64.1	Detailed Description	21
	7.64.2	Constructor & Destructor Documentation	21
		7.64.2.1 Singleton() [1/2]	22
		7.64.2.2 Singleton() [2/2]	22
		7.64.2.3 ~Singleton()	22
	7.64.3	Member Function Documentation	22
		7.64.3.1 get_instance()	22
		7.64.3.2 get_thread_local_instance()	22
		7.64.3.3 operator=()	22
7.65	qpp::ex	ception::SizeMismatch Class Reference	23
	7.65.1	Detailed Description	24
	7.65.2	Member Function Documentation	24
		7.65.2.1 Exception()	24
		7.65.2.2 type_description()	24
7.66	qpp::No	piseType::StateDependent Class Reference	25
	7.66.1	Detailed Description	25
7.67	qpp::No	biseType::StateIndependent Class Reference	25
	7.67.1	Detailed Description	25
7.68	qpp::St	ates Class Reference	25
	7.68.1	Detailed Description	27
	7.68.2	Constructor & Destructor Documentation	28
		7.68.2.1 States()	28
		7.68.2.2 ~States()	
	7.68.3	Member Function Documentation	
	23.0	7.68.3.1 jn()	
		7.68.3.2 mes()	
		7.68.3.3 minus()	

	7.68.3.4	one	<del>)</del> () .										 	٠.		 			329
	7.68.3.5	plus	s() .										 			 			330
	7.68.3.6	zero	၁() .										 			 			330
7.68.4	Friends A	ınd F	?elat	ted F	=unc	tion	Do	cun	nen	tatio	n .		 			 			330
	7.68.4.1	inte	rnal	::Sin	nglete	on<	CO	nst	Sta	tes	> .		 			 			330
7.68.5	Member D	Data	Dod	cume	entat	tion							 			 			330
	7.68.5.1	b00	)										 			 			331
	7.68.5.2	b01											 			 			331
	7.68.5.3	b10	)										 			 			331
	7.68.5.4	b11											 			 			331
	7.68.5.5	GH	<b>Z</b> .										 			 			331
	7.68.5.6	pb0	0 .										 			 			331
	7.68.5.7	pb0	)1 .										 			 			332
	7.68.5.8	pb1	0 .										 			 			332
	7.68.5.9	pb1	1 .										 			 			332
	7.68.5.10	pGl	ΗZ .										 			 			332
	7.68.5.11	pW											 			 			332
	7.68.5.12	px0	١										 			 			332
	7.68.5.13	px1											 			 			333
	7.68.5.14	py0	ı										 			 			333
	7.68.5.15	py1											 			 			333
	7.68.5.16	pz0	١										 			 			333
	7.68.5.17	pz1											 			 			333
	7.68.5.18	w.											 			 			333
	7.68.5.19	x0											 			 			334
	7.68.5.20	<b>x</b> 1											 			 			334
	7.68.5.21	y0											 			 			334
	7.68.5.22	y1											 			 			334
	7.68.5.23	z0											 			 			334
	7.68.5.24	z1											 			 			334

CONTENTS xxxi

7.69	qpp::ex	cception::SubsysMismatchDims Class Reference	35
	7.69.1	Detailed Description	36
	7.69.2	Member Function Documentation	36
		7.69.2.1 Exception()	36
		7.69.2.2 type_description()	36
7.70	qpp::Ti	mer< T, CLOCK_T > Class Template Reference	37
	7.70.1	Detailed Description	38
	7.70.2	Constructor & Destructor Documentation	38
		7.70.2.1 Timer() [1/3]	38
		7.70.2.2 Timer() [2/3]	39
		7.70.2.3 Timer() [3/3]	39
		7.70.2.4 ~Timer()	39
	7.70.3	Member Function Documentation	39
		7.70.3.1 display()	39
		7.70.3.2 get_duration()	40
		7.70.3.3 operator=() [1/2]	40
		7.70.3.4 operator=() [2/2]	40
		7.70.3.5 tic()	41
		7.70.3.6 tics()	41
		7.70.3.7 toc()	41
	7.70.4	Member Data Documentation	41
		7.70.4.1 end	41
		7.70.4.2 start	42
7.71	qpp::ex	cception::TypeMismatch Class Reference	42
	7.71.1	Detailed Description	43
	7.71.2	Member Function Documentation	43
		7.71.2.1 Exception()	43
		7.71.2.2 type_description()	44
7.72	qpp::ex	cception::UndefinedType Class Reference	44
	7.72.1	Detailed Description	45

xxxii CONTENTS

	7.72.2	Member	Function	Docun	nentatio	on .			 	 	 		 ٠.		 	345
		7.72.2.1	Except	ion() .					 	 	 		 	 	 	345
		7.72.2.2	type_d	escription	on() .				 	 	 		 	 	 	346
7.73	qpp::ex	ception::L	Jnknown	Class I	Referer	nce .			 	 	 		 		 	346
	7.73.1	Detailed	Descript	ion .					 	 	 		 		 	347
	7.73.2	Member	Function	Docun	nentatio	on .			 	 	 		 		 	347
		7.73.2.1	Except	ion() .					 	 	 		 		 	347
		7.73.2.2	type_d	escriptio	on() .				 	 	 		 		 	348
7.74	qpp::Q	Circuit::ite	rator::val	ue_type	e_ Clas	ss Re	efere	nce	 	 	 		 		 	348
	7.74.1	Construc	tor & De	structo	r Docur	menta	ation	١	 	 	 		 			349
		7.74.1.1	value_t	:ype_()	[1/2]				 	 	 		 		 	349
		7.74.1.2	value_t	:ype_()	[2/2]				 	 	 		 		 	349
	7.74.2	Member	Function	Docun	nentatio	on .			 	 	 		 		 	350
		7.74.2.1	display	()					 	 	 		 			350
		7.74.2.2	operato	or=() .					 	 	 		 			350
	7.74.3	Member	Data Do	cument	tation .				 	 	 		 			350
		7.74.3.1	gates_i	i <b>p_</b>					 	 	 		 			350
		7.74.3.2	ip						 	 	 		 			351
		7.74.3.3	measu	rements	s_ip				 	 	 		 			351
		7.74.3.4	type						 	 	 		 			351
		7.74.3.5	value_t	:ype_qc	od				 	 	 		 			351
7.75	qpp::ex	ception::Z	ZeroSize	Class F	Referen	nce .			 	 	 		 			352
	7.75.1	Detailed	Descript	ion .					 	 	 		 			353
	7.75.2	Member	Function	i Docun	nentatio	on .			 	 	 		 			353
		7.75.2.1	Except	ion() .					 	 	 		 			353
		7.75.2.2	type_d	escripti	on() .				 	 	 		 			353

CONTENTS xxxiii

8	File I	Documentation	355
	8.1	classes/circuits.h File Reference	355
		8.1.1 Detailed Description	356
	8.2	classes/codes.h File Reference	356
		8.2.1 Detailed Description	356
	8.3	classes/exception.h File Reference	357
		8.3.1 Detailed Description	359
	8.4	classes/gates.h File Reference	359
		8.4.1 Detailed Description	359
	8.5	classes/idisplay.h File Reference	360
		8.5.1 Detailed Description	360
	8.6	classes/init.h File Reference	360
		8.6.1 Detailed Description	361
	8.7	classes/noise.h File Reference	361
		8.7.1 Detailed Description	362
	8.8	classes/random_devices.h File Reference	362
		8.8.1 Detailed Description	362
	8.9	classes/reversible.h File Reference	363
		8.9.1 Detailed Description	363
	8.10	classes/states.h File Reference	363
		8.10.1 Detailed Description	364
	8.11	classes/timer.h File Reference	364
		8.11.1 Detailed Description	365
	8.12	constants.h File Reference	365
		8.12.1 Detailed Description	366
	8.13	entanglement.h File Reference	366
		8.13.1 Detailed Description	368
	8.14	entropies.h File Reference	368
		8.14.1 Detailed Description	369
	8.15	experimental/experimental.h File Reference	369

	8.15.1 Detailed Description	369
8.16	functions.h File Reference	369
	8.16.1 Detailed Description	374
8.17	input_output.h File Reference	374
	8.17.1 Detailed Description	375
8.18	instruments.h File Reference	375
	8.18.1 Detailed Description	376
8.19	internal/classes/iomanip.h File Reference	376
	8.19.1 Detailed Description	377
8.20	internal/classes/singleton.h File Reference	377
	8.20.1 Detailed Description	378
8.21	internal/util.h File Reference	378
	8.21.1 Detailed Description	379
8.22	MATLAB/matlab.h File Reference	380
	8.22.1 Detailed Description	380
8.23	number_theory.h File Reference	380
	8.23.1 Detailed Description	382
8.24	operations.h File Reference	382
	8.24.1 Detailed Description	384
8.25	qpp.h File Reference	384
	8.25.1 Detailed Description	386
	8.25.2 Macro Definition Documentation	386
	8.25.2.1 QPP_UNUSED	386
8.26	random.h File Reference	386
	8.26.1 Detailed Description	387
8.27	statistics.h File Reference	388
	8.27.1 Detailed Description	389
8.28	traits.h File Reference	389
	8.28.1 Detailed Description	390
8.29	types.h File Reference	390
	8.29.1 Detailed Description	391
8.30	/Users/vlad/qpp/README.md File Reference	391
Index		393

# **Chapter 1**

# Quantum++

Version 1.1 - 26 November 2018

**Build status:** 

Chat (questions/issues)

#### **About**

Quantum++ is a modern C++11 general purpose quantum computing library, composed solely of template header files. Quantum++ is written in standard C++11 and has very low external dependencies, using only the Eigen 3 linear algebra header-only template library and, if available, the OpenMP multi-processing library.

Quantum++ is not restricted to qubit systems or specific quantum information processing tasks, being capable of simulating arbitrary quantum processes. The main design factors taken in consideration were the ease of use, high portability, and high performance. The library's simulation capabilities are only restricted by the amount of available physical memory. On a typical machine (Intel i5 8Gb RAM) Quantum++ can successfully simulate the evolution of 25 qubits in a pure state or of 12 qubits in a mixed state reasonably fast.

To report any bugs or ask for additional features/enhancements, please submit an issue with an appropriate label.

If you are interesting in contributing to this project, feel free to contact me. Alternatively, create a custom branch, add your contribution, then finally create a pull request. If I accept the pull request, I will merge your custom branch with the latest development branch. The latter will eventually be merged into a future release version. To contribute, you need to have a solid knowledge of C++ (preferably C++11), including templates and the standard library, a basic knowledge of quantum computing and linear algebra, and working experience with Eigen 3.

For additional Eigen 3 documentation see http://eigen.tuxfamily.org/dox/. For a simple Eigen 3 quick ASCII reference see http://eigen.tuxfamily.org/dox/AsciiQuickReference.txt.

Copyright (c) 2013 - 2019 Vlad Gheorghiu, vgheorgh AT gmail DOT com.

#### License

Quantum++ is distributed under the MIT license. Please see the LICENSE file for more details.

#### Installation instructions and further documentation

Please see the installation guide https://github.com/vsoftco/qpp/blob/master/INSTALL.md "`INSTALL.md`" and the comprehensive Wiki for further documentation and detailed examples.

The official API documentation is available in PDF and HTML formats in the doc folder.

2 Quantum++

# **Chapter 2**

# Namespace Index

# 2.1 Namespace List

Here is a list of all namespaces with brief descriptions:

qpp
Quantum++ main namespace
qpp::exception
Quantum++ exception hierarchy namespace
qpp::experimental
Experimental/test functions/classes, do not use or modify
qpp::internal
Internal utility functions, do not use them directly or modify them
qpp::literals

4 Namespace Index

# **Chapter 3**

# **Hierarchical Index**

# 3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

qpp::internal::Display_Impl
qpp::internal::IOManipEigen
std::exception
qpp::exception::Exception
qpp::exception::CustomException
qpp::exception::DimsInvalid
qpp::exception::DimsMismatchCvector
qpp::exception::DimsMismatchMatrix
qpp::exception::DimsMismatchRvector
qpp::exception::DimsMismatchVector
app::exception::DimsNotEqual
qpp::exception::Duplicates
qpp::exception::InvalidIterator
qpp::exception::MatrixMismatchSubsys
qpp::exception::MatrixNotCvector
qpp::exception::MatrixNotRvector
qpp::exception::MatrixNotSquare
qpp::exception::MatrixNotSquareNorCvector
qpp::exception::MatrixNotSquareNorRvector
qpp::exception::MatrixNotSquareNorVector
qpp::exception::MatrixNotVector
qpp::exception::NoCodeword
qpp::exception::NotBipartite
qpp::exception::NotImplemented
qpp::exception::NotQubitCvector
qpp::exception::NotQubitMatrix
qpp::exception::NotQubitRvector
qpp::exception::NotQubitSubsys
qpp::exception::NotQubitVector
qpp::exception::OutOfRange
qpp::exception::PermInvalid
qpp::exception::PermMismatchDims
qpp::exception::QuditAlreadyMeasured
qpp::exception::SizeMismatch
app::exception::SubsvsMismatchDims

6 Hierarchical Index

qpp::exception::TypeMismatch	
qpp::exception::UndefinedType	
qpp::exception::Unknown	
qpp::exception::ZeroSize	352
false_type	
qpp::is_complex< T >	
qpp::is_iterable < T, typename >	
qpp::Bit_circuit::Gate_count	
qpp::QCircuit::GateStep	
qpp::IDisplay	
qpp::Dynamic_bitset	
qpp::Bit_circuit	
qpp::internal::IOManipEigen	
qpp::internal::IOManipPointer< PointerType >	
qpp::internal::IOManipRange< InputIterator >	
qpp::QCircuit	
qpp::QCircuit::iterator::value_type	
qpp::QEngine	
qpp::Timer< T, CLOCK_T >	
qpp::IJSON	191
qpp::QCircuit	
qpp::QEngine	294
is_base_of	
qpp::is_matrix_expression< Derived >	
qpp::QCircuit::iterator	
$qpp::make\_void < Ts > \ \ldots \$	
qpp::QCircuit::MeasureStep	
qpp::NoiseBase< T >	
qpp::NoiseBase < NoiseType::StateDependent >	
qpp::QubitAmplitudeDampingNoise	
qpp::QubitPhaseDampingNoise	
${\tt qpp::NoiseBase} < {\tt NoiseType::StateIndependent} > \dots $	239
qpp::QubitBitFlipNoise	304
qpp::QubitBitPhaseFlipNoise	306
qpp::QubitDepolarizingNoise	307
qpp::QubitPhaseFlipNoise	310
qpp::QuditDepolarizingNoise	314
qpp::NoiseType	246
$qpp::internal::Singleton < T > \dots \dots$	
qpp::internal::Singleton < const Codes >	320
qpp::Codes	134
qpp::internal::Singleton < const Gates >	320
qpp::Gates	
qpp::internal::Singleton < const Init >	
qpp::Init	
qpp::internal::Singleton< const States >	
qpp::States	325
qpp::internal::Singleton< RandomDevices >	320
qpp::RandomDevices	317
qpp::NoiseType::StateDependent	325
qpp::NoiseType::StateIndependent	
true_type	
$qpp::is\_complex < std::complex < T >> \ \ldots $	208
$qpp::is\_iterable < \hspace{0.1cm} T, \hspace{0.1cm} to\_void < \hspace{0.1cm} decltype(std::declval < \hspace{0.1cm} T \hspace{0.1cm} > ().begin()), \hspace{0.1cm} decltype(std::decltyp$	
>().end()), decltype(*(std::declval< T $>$ ().begin()))>>	210

# **Chapter 4**

# **Class Index**

# 4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

qpp::Bit_circuit	
Classical reversible circuit simulator	129
qpp::Codes	
Const Singleton class that defines quantum error correcting codes	134
qpp::exception::CustomException	
Custom exception	137
qpp::exception::DimsInvalid	
Invalid dimension(s) exception	140
qpp::exception::DimsMismatchCvector	
Dimension(s) mismatch column vector size exception	142
qpp::exception::DimsMismatchMatrix	
Dimension(s) mismatch matrix size exception	144
qpp::exception::DimsMismatchRvector	
Dimension(s) mismatch row vector size exception	146
qpp::exception::DimsMismatchVector	
Dimension(s) mismatch vector size exception	148
qpp::exception::DimsNotEqual	
Dimensions not equal exception	150
qpp::internal::Display_Impl	152
qpp::exception::Duplicates	
System (e.g. std::vector) has duplicates exception	153
qpp::Dynamic_bitset	
Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std←	
::bitset <n>)</n>	155
qpp::exception::Exception	
Base class for generating Quantum++ custom exceptions	166
qpp::Bit_circuit::Gate_count	170
qpp::Gates	
Const Singleton class that implements most commonly used gates	172
qpp::QCircuit::GateStep	
One step consisting only of gates/operators in the circuit	185
qpp::IDisplay	
Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream&	& os) cons
188	
qpp::IJSON	
Abstract class (interface) that mandates the definition of very basic JSON serialization support	191

8 Class Index

qpp::Init	
Const Singleton class that performs additional initializations/cleanups	193
qpp::exception::InvalidIterator	
Invalid iterator	
qpp::internal::IOManipEigen	197
qpp::internal::IOManipPointer< PointerType >	200
qpp::internal::IOManipRange< InputIterator >	203
qpp::is_complex < T >	
Checks whether the type is a complex type	207
qpp::is_complex < std::complex < T > >	
Checks whether the type is a complex number type, specialization for complex types	208
qpp::is_iterable< T, typename >	
Checks whether T is compatible with an STL-like iterable container	209
qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval< T >().end()), d	ecltype(*(std::declval<
Checks whether T is compatible with an STL-like iterable container, specialization for STL-like	
iterable containers	210
qpp::is_matrix_expression< Derived >	
Checks whether the type is an Eigen matrix expression	211
qpp::QCircuit::iterator	
Quantum circuit bound-checking (safe) iterator	212
qpp::make_void< Ts >	
Helper for qpp::to_void<> alias template	217
qpp::exception::MatrixMismatchSubsys	211
Matrix mismatch subsystems exception	218
qpp::exception::MatrixNotCvector	210
Matrix is not a column vector exception	220
qpp::exception::MatrixNotRvector	220
	222
Matrix is not a row vector exception	222
qpp::exception::MatrixNotSquare	004
Matrix is not square exception	224
qpp::exception::MatrixNotSquareNorCvector	000
Matrix is not square nor column vector exception	226
qpp::exception::MatrixNotSquareNorRvector	
Matrix is not square nor row vector exception	228
qpp::exception::MatrixNotSquareNorVector	
Matrix is not square nor vector exception	230
qpp::exception::MatrixNotVector	
Matrix is not a vector exception	232
qpp::QCircuit::MeasureStep	
One step consisting only of measurements in the circuit	234
qpp::exception::NoCodeword	
Codeword does not exist exception	237
qpp::NoiseBase< T >	
Base class for all noise models, derive your particular noise model	239
qpp::NoiseType	
Contains template tags used to specify the noise type	246
qpp::exception::NotBipartite	
Not bi-partite exception	247
qpp::exception::NotImplemented	
Code not yet implemented	249
qpp::exception::NotQubitCvector	
Column vector is not 2 x 1 exception	251
qpp::exception::NotQubitMatrix	
Matrix is not 2 x 2 exception	253
qpp::exception::NotQubitRvector	
Row vector is not 1 x 2 exception	255
qpp::exception::NotQubitSubsys	200
Subsystems are not qubits exception	257
Casofotomo aro not quento exception	

4.1 Class List

qpp::exception::NotQubitVector	
Vector is not 2 x 1 nor 1 x 2 exception	259
qpp::exception::OutOfRange	
Argument out of range exception	261
qpp::exception::PermInvalid	
Invalid permutation exception	263
qpp::exception::PermMismatchDims	
Permutation mismatch dimensions exception	265
qpp::QCircuit	
Quantum circuit class	267
qpp::QEngine	
Quantum circuit engine, executes qpp::QCircuit	294
qpp::QubitAmplitudeDampingNoise	
Qubit amplitude damping noise, as described in Nielsen and Chuang	303
qpp::QubitBitFlipNoise	
Qubit bit flip noise	304
qpp::QubitBitPhaseFlipNoise	
Qubit bit-phase flip (dephasing) noise	306
qpp::QubitDepolarizingNoise	
Qubit depolarizing noise	307
qpp::QubitPhaseDampingNoise	
Qubit phase damping noise, as described in Nielsen and Chuang	309
qpp::QubitPhaseFlipNoise	
Qubit phase flip (dephasing) noise	310
qpp::exception::QuditAlreadyMeasured	
Qudit was already measured exception	312
qpp::QuditDepolarizingNoise	
Qudit depolarizing noise	314
qpp::RandomDevices	
Singleton class that manages the source of randomness in the library	317
qpp::internal::Singleton< T >	
Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously	
recurring template pattern)	320
qpp::exception::SizeMismatch	
Size mismatch exception	323
qpp::NoiseType::StateDependent	
Template tag, used whenever the noise is state-dependent	325
qpp::NoiseType::StateIndependent	
Template tag, used whenever the noise is state-independent	325
qpp::States	
Const Singleton class that implements most commonly used states	325
qpp::exception::SubsysMismatchDims	
Subsystems mismatch dimensions exception	335
qpp::Timer< T, CLOCK_T >	
Chronometer	337
qpp::exception::TypeMismatch	
Type mismatch exception	342
qpp::exception::UndefinedType	
Not defined for this type exception	344
qpp::exception::Unknown	
Unknown exception	346
qpp::QCircuit::iterator::value_type	348
qpp::exception::ZeroSize	
Object has zero size exception	352

10 Class Index

# **Chapter 5**

# File Index

# 5.1 File List

Here is a list of all files with brief descriptions:

constant	ts.h	
	Constants	365
entangle	ement.h	
	Entanglement functions	366
entropie	es.h	
	Entropy functions	368
functions	s.h	
	Generic quantum computing functions	369
input_ou	utput.h	
	Input/output functions	374
instrume	ents.h	
	Measurement functions	375
number_	_theory.h	
	Number theory functions	380
operatio	ins.h	
	Quantum operation functions	382
qpp.h		
	Quantum++ main header file, includes all other necessary headers	384
random.	.h	
	Randomness-related functions	386
statistics		
	Statistics functions	388
traits.h		
	Type traits	389
types.h		
	Type aliases	390
classes/	/circuits.h	
	Support for qudit quantum circuits	355
classes/		
	Quantum error correcting codes	356
classes/	/exception.h	
	Exceptions	357
classes/	'gates.h	
	Quantum gates	359

12 File Index

classes/idisplay.h	
Display interface via the non-virtual interface (NVI) and very basic JSON serialization support	
interface	360
classes/init.h	
Initialization	360
classes/noise.h	
Noise models	361
classes/random_devices.h	
Random devices	362
classes/reversible.h	
Support for classical reversible circuits	363
classes/states.h	
Quantum states	363
classes/timer.h	
Timing	364
experimental/experimental.h	
Experimental/test functions/classes	369
internal/util.h	
Internal utility functions	378
internal/classes/iomanip.h	
Input/output manipulators	376
internal/classes/singleton.h	
Singleton pattern via CRTP	377
MATLAB/matlab.h	
Input/output interfacing with MATLAB	380

# **Chapter 6**

# **Namespace Documentation**

# 6.1 qpp Namespace Reference

Quantum++ main namespace.

# **Namespaces**

· exception

Quantum++ exception hierarchy namespace.

· experimental

Experimental/test functions/classes, do not use or modify.

internal

Internal utility functions, do not use them directly or modify them.

literals

# Classes

· class Bit\_circuit

Classical reversible circuit simulator.

• class Codes

const Singleton class that defines quantum error correcting codes

· class Dynamic\_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

· class Gates

const Singleton class that implements most commonly used gates

class IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

class IJSON

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

class Init

const Singleton class that performs additional initializations/cleanups

· struct is complex

Checks whether the type is a complex type.

- struct is\_complex< std::complex< T > >

Checks whether the type is a complex number type, specialization for complex types.

· struct is\_iterable

Checks whether T is compatible with an STL-like iterable container.

 $\bullet \ \ struct\ is\_iterable < T,\ to\_void < \ decltype(std::declval < T>().begin()),\ decltype(std::declval < T>().end()),\ decltype(*(std::declval < T>().end())),\ decltype(*(std::declval < T>().end()$ 

Checks whether T is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

• struct is\_matrix\_expression

Checks whether the type is an Eigen matrix expression.

· struct make void

Helper for qpp::to\_void<> alias template.

· class NoiseBase

Base class for all noise models, derive your particular noise model.

class NoiseType

Contains template tags used to specify the noise type.

class QCircuit

Quantum circuit class.

· class QEngine

Quantum circuit engine, executes qpp::QCircuit.

· class QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

• class QubitBitFlipNoise

Qubit bit flip noise.

• class QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

· class QubitDepolarizingNoise

Qubit depolarizing noise.

· class QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

class QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

· class QuditDepolarizingNoise

Qudit depolarizing noise.

· class RandomDevices

Singleton class that manages the source of randomness in the library.

· class States

const Singleton class that implements most commonly used states

· class Timer

Chronometer.

# **Typedefs**

```
• template<typename... Ts>
```

```
using to_void = typename make_void < Ts... >::type
```

Alias template that implements the proposal for void\_t.

• using idx = std::size t

Non-negative integer index, make sure you use an unsigned type.

• using bigint = long long int

Big integer.

• using cplx = std::complex< double >

Complex number in double precision.

• using ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector. using bra = Eigen::RowVectorXcd Complex (double precision) dynamic Eigen row vector. • using cmat = Eigen::MatrixXcd Complex (double precision) dynamic Eigen matrix. using dmat = Eigen::MatrixXd Real (double precision) dynamic Eigen matrix. template<typename Scalar > using dyn mat = Eigen::Matrix < Scalar, Eigen::Dynamic, Eigen::Dynamic > Dynamic Eigen matrix over the field specified by Scalar. • template<typename Scalar > using dyn\_col\_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 > Dynamic Eigen column vector over the field specified by Scalar. template<typename Scalar > using dyn\_row\_vect = Eigen::Matrix < Scalar, 1, Eigen::Dynamic > Dynamic Eigen row vector over the field specified by Scalar. **Functions** • constexpr cplx operator"" \_i (long double x) noexcept User-defined literal for complex  $i = \sqrt{-1}$  (real overload) cplx omega (idx D) D-th root of unity. • template<typename Derived > dyn\_col\_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt coefficients of the bi-partite pure state A. template<typename Derived > dyn\_col\_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2) Schmidt coefficients of the bi-partite pure state A. template<typename Derived > cmat schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt basis on Alice side. • template<typename Derived > cmat schmidtA (const Eigen::MatrixBase< Derived > &A, idx d=2) Schmidt basis on Alice side. template<typename Derived > cmat schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt basis on Bob side. template<typename Derived > cmat schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2) Schmidt basis on Bob side. template<typename Derived > std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims) Schmidt probabilities of the bi-partite pure state A.

std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)

double entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)

template<typename Derived >

template<typename Derived >

Schmidt probabilities of the bi-partite pure state A.

Entanglement of the bi-partite pure state A.

```
• template<typename Derived >
  double entanglement (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Entanglement of the bi-partite pure state A.
template<typename Derived >
  double gconcurrence (const Eigen::MatrixBase< Derived > &A)
     G-concurrence of the bi-partite pure state A.
template<typename Derived >
  double negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Negativity of the bi-partite mixed state A.

    template < typename Derived >

  double negativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Negativity of the bi-partite mixed state A.

    template < typename Derived >

  double lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Logarithmic negativity of the bi-partite mixed state A.
• template<typename Derived >
  double lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Logarithmic negativity of the bi-partite mixed state A.
• template<typename Derived >
  double concurrence (const Eigen::MatrixBase< Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.
• template<typename Derived >
  double entropy (const Eigen::MatrixBase< Derived > &A)
      von-Neumann entropy of the density matrix A

    double entropy (const std::vector< double > &prob)

     Shannon entropy of the probability distribution prob.

    template<typename Derived >

  double renyi (const Eigen::MatrixBase< Derived > &A, double alpha)
      Renyi- \alpha entropy of the density matrix A, for \alpha \geq 0.

    double renyi (const std::vector< double > &prob, double alpha)

     Renyi- \alpha entropy of the probability distribution prob, for \alpha > 0.

    template<typename Derived >

  double tsallis (const Eigen::MatrixBase< Derived > &A, double q)
      Tsallis- q entropy of the density matrix A, for q > 0.

    double tsallis (const std::vector< double > &prob, double q)

      Tsallis- q entropy of the probability distribution prob, for q > 0.
• template<typename Derived >
  double qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx > &subsysB, const std::vector< idx > &dims)
     Quantum mutual information between 2 subsystems of a composite system.

    template<typename Derived >

  double gmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx> &subsysB, idx d=2)
      Quantum mutual information between 2 subsystems of a composite system.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > transpose (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > adjoint (const Eigen::MatrixBase< Derived > &A)
     Adjoint.
```

```
    template<typename Derived >

  dyn_mat< typename Derived::Scalar > inverse (const Eigen::MatrixBase< Derived > &A)

    template<typename Derived >

  Derived::Scalar trace (const Eigen::MatrixBase< Derived > &A)
      Trace
• template<typename Derived >
  Derived::Scalar det (const Eigen::MatrixBase< Derived > &A)
     Determinant.

    template<typename Derived >

  Derived::Scalar logdet (const Eigen::MatrixBase< Derived > &A)
     Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar sum (const Eigen::MatrixBase< Derived > &A)
      Element-wise sum of A.
• template<typename Derived >
  Derived::Scalar prod (const Eigen::MatrixBase< Derived > &A)
     Element-wise product of A.

    template<typename Derived >

  double norm (const Eigen::MatrixBase< Derived > &A)
     Frobenius norm.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > normalize (const Eigen::MatrixBase< Derived > &A)
     Normalizes state vector (column or row vector) or density matrix.

    template<typename Derived >

  std::pair < dyn_col_vect < cplx >, cmat > eig (const Eigen::MatrixBase < Derived > &A)
     Full eigen decomposition.

    template<typename Derived >

  dyn_col_vect< cplx > evals (const Eigen::MatrixBase< Derived > &A)
     Eigenvalues.

    template<typename Derived >

  cmat evects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors.

    template<typename Derived >

  std::pair< dyn_col_vect< double >, cmat > heig (const Eigen::MatrixBase< Derived > &A)
     Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > hevals (const Eigen::MatrixBase< Derived > &A)
     Hermitian eigenvalues.
• template<typename Derived >
  cmat hevects (const Eigen::MatrixBase< Derived > &A)
     Eigenvectors of Hermitian matrix.
• template<typename Derived >
  std::tuple< cmat, dyn_col_vect< double >, cmat > svd (const Eigen::MatrixBase< Derived > &A)
     Full singular value decomposition.

    template<typename Derived >

  dyn_col_vect< double > svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.
• template<typename Derived >
  cmat svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.

    template<typename Derived >

  cmat svdV (const Eigen::MatrixBase< Derived > &A)
```

Direct sum.

```
Right singular vectors.
• template<typename Derived >
  cmat funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)

    template<typename Derived >

  cmat sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.

    template<typename Derived >

  cmat absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.

    template<typename Derived >

  cmat expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.

    template<typename Derived >

  cmat logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.
• template<typename Derived >
  cmat sinm (const Eigen::MatrixBase< Derived > &A)
     Matrix sin.

    template<typename Derived >

  cmat cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.
template<typename Derived >
  cmat spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.
• template<typename Derived >
  \label{eq:const_equation} \mbox{dyn\_mat} < \mbox{typename Derived::Scalar} > \mbox{powm (const Eigen::MatrixBase} < \mbox{Derived} > \&\mbox{A, idx n)}
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.
• template<typename Derived >
  double schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const type-
  name Derived::Scalar &))
     Functor.
template<typename T >
  dyn_mat< typename T::Scalar > kron (const T &head)
     Kronecker product.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > kron (const T &head, const Args &... tail)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > kron (const std::vector< Derived > &As)
     Kronecker product.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > kron (const std::initializer_list< Derived > &As)
     Kronecker product.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Kronecker power.

    template<typename T >

  dyn_mat< typename T::Scalar > dirsum (const T &head)
```

```
• template<typename T, typename... Args>
  dyn_mat< typename T::Scalar > dirsum (const T &head, const Args &... tail)
     Direct sum.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > dirsum (const std::vector< Derived > &As)

    template<typename Derived >

  dyn mat< typename Derived::Scalar > dirsum (const std::initializer list< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > reshape (const Eigen::MatrixBase< Derived > &A, idx rows, idx
  cols)
     Reshape.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > comm (const Eigen::MatrixBase< Derived1 > &A, const Eigen::⊷
  MatrixBase< Derived2 > &B)
     Commutator.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > prj (const Eigen::MatrixBase< Derived > &A)
     Projector.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > grams (const std::vector< Derived > &As)
     Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > grams (const std::initializer_list< Derived > &As)
      Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > grams (const Eigen::MatrixBase< Derived > &A)
     Gram-Schmidt orthogonalization.

    std::vector< idx > n2multiidx (idx n, const std::vector< idx > &dims)

     Non-negative integer index to multi-index.

    idx multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

     Multi-index to non-negative integer index.

    ket mket (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Multi-partite qudit ket.

    ket mket (const std::vector< idx > &mask, idx d=2)

     Multi-partite qudit ket.

    cmat mprj (const std::vector < idx > &mask, const std::vector < idx > &dims)

     Projector onto multi-partite qudit ket.

    cmat mprj (const std::vector < idx > &mask, idx d=2)

     Projector onto multi-partite qudit ket.
• template<typename InputIterator >
  std::vector< double > abssq (InputIterator first, InputIterator last)
```

Computes the absolute values squared of an STL-like range of complex numbers.

• template<typename Container >

std::vector< double > abssq (const Container &c, typename std::enable\_if< is\_iterable< Container >::value >::type \*=nullptr)

Computes the absolute values squared of an STL-like container.

template<typename Derived >

```
std::vector< double > abssq (const Eigen::MatrixBase< Derived > &A)
```

Computes the absolute values squared of an Eigen expression.

template<typename InputIterator >

std::iterator\_traits< InputIterator >::value\_type sum (InputIterator first, InputIterator last)

Element-wise sum of an STL-like range.

• template<typename Container >

Container::value\_type sum (const Container &c, typename std::enable\_if< is\_iterable< Container >::value >::type \*=nullptr)

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

std::iterator traits < InputIterator >::value type prod (InputIterator first, InputIterator last)

Element-wise product of an STL-like range.

• template<typename Container >

Container::value\_type prod (const Container &c, typename std::enable\_if< is\_iterable< Container >::value >::type \*=nullptr)

Element-wise product of the elements of an STL-like container.

template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > rho2pure (const Eigen::MatrixBase< Derived > &A)
```

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

std::vector< idx > complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

• template<typename Derived >

```
std::vector< double > rho2bloch (const Eigen::MatrixBase< Derived > &A)
```

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

• template<typename Derived >

internal::IOManipEigen disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)

Eigen expression ostream manipulator.

internal::IOManipEigen disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

• template<typename InputIterator >

internal::IOManipRange < InputIterator > disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")

Range ostream manipulator.

 $\bullet \ \ \text{template}{<} \text{typename Container} >$ 

internal::IOManipRange< typename Container::const\_iterator > disp (const Container &c, const std::string &separator, const std::string &start="[", const std::string &end="]", typename std::enable\_if< is\_iterable< Container >::value >::type \*=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

template<typename PointerType >

internal::IOManipPointer< PointerType > disp (const PointerType \*p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")

C-style pointer ostream manipulator.

template<typename Derived >

```
void save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)
```

Saves Eigen expression to a binary file (internal format) in double precision.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.

• template<typename Derived >

 $\label{lem:dyn_col_vect} $$ \displaystyle \operatorname{dyn_col_vect} < \operatorname{typename \ Derived}::Scalar > ip (const \ Eigen::MatrixBase < \operatorname{Derived} > & phi, const \ Eigen:: \longleftrightarrow \\ \operatorname{MatrixBase} < \operatorname{Derived} > & psi, const \ std::vector < idx > & subsys, const \ std::vector < idx > & dims) \\ $$ \displaystyle \operatorname{dyn_col_vect} < \operatorname{dyn_col_v$ 

Generalized inner product.

• template<typename Derived >

dyn\_col\_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer\_list< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer\_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$ 

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > measure\_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

template<typename Derived >

 $std::tuple < std::vector < idx >, \ double, \ cmat > measure\_seq \ (const \ Eigen::MatrixBase < Derived > \&A, \\ std::vector < idx > target, \ idx \ d=2)$ 

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

ullet template<typename Derived >

 $std::enable\_if < std::is\_same < typename Derived::Scalar, cplx >::value, dyn\_mat < cplx > ::type \\ loadMATLAB (const std::string &mat\_file, const std::string &var\_name)$ 

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable\_if<!std::is\_same< typename Derived::Scalar, cplx >::value, dyn\_mat< typename Derived::

Scalar > >::type loadMATLAB (const std::string &mat\_file, const std::string &var\_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >

std::enable\_if< std::is\_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat\_file, const std::string &var\_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

template<typename Derived >

std::enable\_if< !std::is\_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat\_file, const std::string &var\_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

std::vector< int > x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

bigint gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > invperm (const std::vector< idx > &perm)

Inverse permutation.

• std::vector< idx > compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

std::vector< bigint > factors (bigint a)

Prime factor decomposition.

• bigint modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

bigint modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple < bigint, bigint, bigint > egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint modinv (bigint a, bigint p)

Modular inverse of a mod p.

bool isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

bigint randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

std::vector< std::pair< int, int > > convergents (const std::vector< int > &cf)

Convergents

std::vector< std::pair< int, int > > convergents (double x, idx N)

Convergents.

• template<typename Derived1 , typename Derived2 >

dyn\_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, const
std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

- template<typename Derived1 , typename Derived2 >

dyn\_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, idx
d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

```
dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)
```

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

template<typename Derived >

cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, const std::vector< idx > &dims)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

• template<typename Derived >

```
cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, idx d=2)
```

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat kraus2super (const std::vector < cmat > &Ks)

Superoperator matrix.

cmat kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector< cmat > choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

template<typename Derived >

```
\label{lem:dyn_mat}  \mbox{dyn\_mat} < \mbox{typename Derived::Scalar} > \mbox{ptrace1} \mbox{ (const Eigen::MatrixBase} < \mbox{Derived} > \&\mbox{A, const std} \\ \mbox{::vector} < \mbox{idx} > \&\mbox{dims})
```

Partial trace.

 $\bullet \ \ {\sf template}{<} {\sf typename \ Derived} >$ 

```
dyn_mat< typename Derived::Scalar > ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.
```

template<typename Derived >

```
\frac{dyn\_mat<}{typename} \ Derived::Scalar > ptrace2 \ (const \ Eigen::MatrixBase< \ Derived > \&A, \ const \ std \\ \because vector < idx > \&dims)
```

Partial trace.

• template<typename Derived >

```
dyn_mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)
```

Partial trace.

ullet template<typename Derived >

 $\frac{dyn_mat}{dx}$  typename Derived::Scalar >  $\frac{dyn_mat}{dx}$  (const Eigen::MatrixBase < Derived > &A, const std::vector <  $\frac{dx}{dx}$  > &target, const std::vector <  $\frac{dx}{dx}$  > &dims)

Partial trace.

ullet template<typename Derived >

dyn\_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector
idx > &target, idx d=2)

Partial trace.

template<typename Derived >

Partial transpose.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > ptranspose (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial transpose.

• template<typename Derived >

Subsystem permutation.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > syspermute (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &perm, idx d=2)

Subsystem permutation.

template<typename Derived >

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > applyTFQ (const Eigen::MatrixBase< Derived > &A, const std↔ ::vector< idx > &target, idx d=2, bool swap=true)

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn\_col\_vect< typename Derived::Scalar > TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool
swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

template<typename Derived >

dyn\_col\_vect< typename Derived::Scalar > QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool
swap=true)

Qudit quantum Fourier transform.

• double rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

• bigint rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx randidx (idx a=std::numeric\_limits < idx >::min(), idx b=std::numeric\_limits < idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$ 

Derived rand (idx rows, idx cols, double a=0, double b=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

• template<>

dmat rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (gpp::dmat)

• template<>

cmat rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived randn (idx rows, idx cols, double mean=0, double sigma=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

dmat randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

template<>

cmat randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

• double randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

• cmat randU (idx D=2)

Generates a random unitary matrix.

· cmat randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat randH (idx D=2)

Generates a random Hermitian matrix.

• ket randket (idx D=2)

Generates a random normalized ket (pure state vector)

cmat randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.

std::vector< double > uniform (idx N)

Uniform probability distribution vector.

std::vector< double > marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > marginalY (const dmat &probXY)

Marginal distribution.

 $\bullet \ \ \text{template}{<} \text{typename Container} >$ 

double avg (const std::vector< double > &prob, const Container &X, typename std::enable\_if< is\_iterable<
Container >::value >::type \*=nullptr)

Average.

• template<typename Container >

double cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable\_if< is iterable< Container >::value >::type \*=nullptr)

Covariance.

• template<typename Container >

double var (const std::vector< double > &prob, const Container &X, typename std::enable\_if< is\_iterable<
Container >::value >::type \*=nullptr)

Variance.

template<typename Container >
 double sigma (const std::vector< double > &prob, const Container &X, typename std::enable\_if<
 is\_iterable< Container >::value >::type \*=nullptr)

Standard deviation.

• template<typename Container >

double cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable\_if< is\_iterable< Container >::value >::type \*=nullptr)

Correlation.

#### **Variables**

• constexpr double chop = 1e-10

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

constexpr double eps = std::numeric\_limits<double>::epsilon()

Used to decide whether a number or expression in double precision is zero or not for the purpose of a specific computation.

• constexpr idx maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

constexpr double pi = 3.141592653589793238462643383279502884

 $\pi$ 

constexpr double ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

constexpr double infty = std::numeric\_limits<double>::max()

Used to denote infinity in double precision.

const idx idx infty = static cast<idx>(-1)

Used to denote the largest unsigned index.

# 6.1.1 Detailed Description

Quantum++ main namespace.

# 6.1.2 Typedef Documentation

#### 6.1.2.1 bigint

```
using qpp::bigint = typedef long long int
```

Big integer.

#### 6.1.2.2 bra

```
using qpp::bra = typedef Eigen::RowVectorXcd
```

Complex (double precision) dynamic Eigen row vector.

```
6.1.2.3 cmat
```

```
using qpp::cmat = typedef Eigen::MatrixXcd
```

Complex (double precision) dynamic Eigen matrix.

# 6.1.2.4 cplx

```
using qpp::cplx = typedef std::complex<double>
```

Complex number in double precision.

#### 6.1.2.5 dmat

```
using qpp::dmat = typedef Eigen::MatrixXd
```

Real (double precision) dynamic Eigen matrix.

# 6.1.2.6 dyn\_col\_vect

```
template<typename Scalar >
using qpp::dyn_col_vect = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, 1>
```

Dynamic Eigen column vector over the field specified by Scalar.

# Example:

```
// type of colvect is Eigen::Matrix<float, Eigen::Dynamic, 1>
dyn_col_vect<float> colvect(2);
```

# 6.1.2.7 dyn\_mat

```
template<typename Scalar >
using qpp::dyn_mat = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, Eigen::Dynamic>
```

Dynamic Eigen matrix over the field specified by Scalar.

# Example:

```
// type of mat is Eigen::Matrix<float, Eigen::Dynamic, Eigen::Dynamic>
dyn_mat<float> mat(2, 3);
```

```
6.1.2.8 dyn_row_vect
```

```
template<typename Scalar >
using qpp::dyn_row_vect = typedef Eigen::Matrix<Scalar, 1, Eigen::Dynamic>
```

Dynamic Eigen row vector over the field specified by Scalar.

# Example:

```
// type of rowvect is Eigen::Matrix<float, 1, Eigen::Dynamic>
dyn_row_vect<float> rowvect(3);
```

#### 6.1.2.9 idx

```
using qpp::idx = typedef std::size_t
```

Non-negative integer index, make sure you use an unsigned type.

#### 6.1.2.10 ket

```
using qpp::ket = typedef Eigen::VectorXcd
```

Complex (double precision) dynamic Eigen column vector.

#### 6.1.2.11 to\_void

```
template<typename... Ts>
using qpp::to_void = typedef typename make_void<Ts...>::type
```

Alias template that implements the proposal for void\_t.

#### See also

```
http://www.open-std.org/jtc1/sc22/wg21/docs/papers/2014/n3911
```

# 6.1.3 Function Documentation

#### 6.1.3.1 absm()

Matrix absolute value.

#### **Parameters**

```
A Eigen expression
```

# Returns

Matrix absolute value of A

Computes the absolute values squared of an STL-like range of complex numbers.

#### **Parameters**

	Iterator to the first element of the range
last	Iterator to the last element of the range

InputIterator last )

# Returns

Real vector consisting of the range absolute values squared

```
6.1.3.3 abssq() [2/3]
```

Computes the absolute values squared of an STL-like container.

#### **Parameters**

```
c STL-like container
```

#### Returns

Real vector consisting of the container's absolute values squared

Computes the absolute values squared of an Eigen expression.

#### **Parameters**

```
A Eigen expression
```

#### Returns

Real vector consisting of the absolute values squared

#### 6.1.3.5 adjoint()

# Adjoint.

#### **Parameters**

```
A Eigen expression
```

#### Returns

Adjoint (Hermitian conjugate) of A, as a dynamic matrix over the same scalar field as A

# 6.1.3.6 anticomm()

Anti-commutator.

#### See also

qpp::comm()

Anti-commutator  $\{A,B\} = AB + BA$ . Both A and B must be Eigen expressions over the same scalar field.

#### **Parameters**

Α	Eigen expression
В	Eigen expression

#### Returns

Anti-commutator AB + BA, as a dynamic matrix over the same scalar field as A

# **6.1.3.7** apply() [1/5]

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

#### Note

The dimension of the gate A must match the dimension of target

#### **Parameters**

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

#### Returns

Gate A applied to the part target of state

# **6.1.3.8** apply() [2/5]

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

#### Note

The dimension of the gate A must match the dimension of target

#### **Parameters**

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

# Returns

Gate A applied to the part target of state

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

#### **Parameters**

Α	Eigen expression
Ks	Set of Kraus operators

#### Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*.

#### **Parameters**

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes where the Kraus operators Ks are applied
dims	Dimensions of the multi-partite system

# Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A* 

#### **Parameters**

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes where the Kraus operators Ks are applied
d	Subsystem dimensions

### Returns

Output density matrix after the action of the channel

# 6.1.3.12 applyCTRL() [1/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

#### See also

```
qpp::Gates::CTRL()
```

#### Note

The dimension of the gate *A* must match the dimension of *target*. Also, all control subsystems in *ctrl* must have the same dimension.

#### **Parameters**

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

#### Returns

CTRL-A gate applied to the part target of state

# 6.1.3.13 applyCTRL() [2/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

# See also

```
qpp::Gates::CTRL()
```

#### Note

The dimension of the gate A must match the dimension of target

# **Parameters**

state	Eigen expression
Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

#### Returns

CTRL-A gate applied to the part target of state

# 6.1.3.14 applyQFT()

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

#### **Parameters**

Α	Eigen expression
target	Subsystem indexes where the QFT is applied
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

# Returns

Qudit Quantum Fourier transform applied to the part target of A

# 6.1.3.15 applyTFQ()

Applies the inverse (adjoint) qudit quantum Fourier transform to the part *target* of the multi-partite state vector or density matrix *A*.

#### **Parameters**

Α	Eigen expression
target	Subsystem indexes where the TFQ is applied
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

#### Returns

Inverse (adjoint) qudit Quantum Fourier transform applied to the part target of A

# 6.1.3.16 avg()

#### Average.

#### **Parameters**

prob	Real probability vector representing the probability distribution of $X$
Χ	Real random variable values represented by an STL-like container

# Returns

Average of X

# 6.1.3.17 bloch2rho()

Computes the density matrix corresponding to the 3-dimensional real Bloch vector *r*.

# See also

qpp::rho2bloch()

#### **Parameters**

r 3-dimensional real vector

# Returns

Qubit density matrix

#### 6.1.3.18 choi2kraus()

Orthogonal Kraus operators from Choi matrix.

See also

qpp::kraus2choi()

Extracts a set of orthogonal (under Hilbert-Schmidt operator norm) Kraus operators from the Choi matrix A

Note

The Kraus operators satisfy  $Tr(K_i^{\dagger}K_j)=\delta_{ij}$  for all  $i\neq j$ 

#### **Parameters**



# Returns

Set of orthogonal Kraus operators


# 6.1.3.19 choi2super()

Converts Choi matrix to superoperator matrix.

See also

qpp::super2choi()

# **Parameters**



# Returns

Superoperator matrix

#### 6.1.3.20 comm()

Commutator.

#### See also

qpp::anticomm()

Commutator [A, B] = AB - BA. Both A and B must be Eigen expressions over the same scalar field.

#### **Parameters**

Α	Eigen expression
В	Eigen expression

#### Returns

Commutator AB - BA, as a dynamic matrix over the same scalar field as A

# 6.1.3.21 complement()

Constructs the complement of a subsystem vector.

#### **Parameters**

subsys	Subsystem vector
n	Total number of systems

# Returns

Complement of *subsys* with respect to the set  $\{0, 1, \dots, n-1\}$ 

# 6.1.3.22 compperm()

Compose permutations.

# **Parameters**

perm	Permutation
sigma	Permutation

#### Returns

Composition of the permutations *perm* o *sigma* = perm(sigma)

#### 6.1.3.23 concurrence()

Wootters concurrence of the bi-partite qubit mixed state A.

#### **Parameters**

```
A Eigen expression
```

# Returns

Wootters concurrence

# 6.1.3.24 conjugate()

Complex conjugate.

# **Parameters**

```
A Eigen expression
```

#### Returns

Complex conjugate of A, as a dynamic matrix over the same scalar field as A

#### 6.1.3.25 contfrac2x()

Real representation of a simple continued fraction.

#### See also

```
qpp::x2contfrac()
```

#### Note

If N is greater than the size of cf (by default it is), then all terms in cf are considered.

#### **Parameters**

	Integer vector containing the simple continued fraction expansion
Ν	Number of terms considered in the continued fraction expansion.

# Returns

Real representation of the simple continued fraction

# **6.1.3.26** convergents() [1/2]

```
std::vector<std::pair<int, int> > qpp::convergents ( const std::vector< int > & cf ) [inline]
```

Convergents.

# See also

```
qpp::contfrac2x() and qpp::x2contfrac()
```

#### **Parameters**

```
cf Continued fraction
```

### Returns

Vector of convergents pairs  $(a_k, b_k)$  that approximate the number represented by the continued fraction

#### 6.1.3.27 convergents() [2/2]

```
std::vector<std::pair<int, int> > qpp::convergents ( double x, idx N) [inline]
```

# Convergents.

#### See also

```
qpp::contfrac2x() and qpp::x2contfrac()
```

#### Note

In the continued fraction expansion of x has less terms than N, then the series of convergents is truncated to the number of terms in the continued fraction expansion of x.

#### **Parameters**

Х	Real number
Ν	Number of convergents.

#### Returns

Vector of convergents pairs  $(a_k,b_k)$  that approximate the number  $\emph{x}$ 

### 6.1.3.28 cor()

# Correlation.

#### **Parameters**

probXY	Real matrix representing the joint probability distribution of $X$ and $Y$ in lexicographical order ( $X$ labels the rows, $Y$ labels the columns)
X	Real random variable values represented by an STL-like container
Y	Real random variable values represented by an STL-like container

# Returns

Correlation of X and Y

### 6.1.3.29 cosm()

Matrix cos.

#### **Parameters**

```
A Eigen expression
```

#### Returns

Matrix cosine of A

# 6.1.3.30 cov()

#### Covariance.

# **Parameters**

probXY	Real matrix representing the joint probability distribution of $X$ and $Y$ in lexicographical order ( $X$ labels the rows, $Y$ labels the columns)
Χ	Real random variable values represented by an STL-like container
Y	Real random variable values represented by an STL-like container

#### Returns

Covariance of X and Y

# 6.1.3.31 cwise()

Functor.

# **Parameters**

Α	Eigen expression
f	Pointer-to-function from scalars of A to OutputScalar

#### Returns

Component-wise f(A), as a dynamic matrix over the *OutputScalar* scalar field

#### 6.1.3.32 det()

#### Determinant.

#### **Parameters**

A Eigen expression

### Returns

Determinant of A, as a scalar over the same scalar field as A. Returns  $\pm \infty$  when the determinant overflows/underflows.

```
6.1.3.33 dirsum() [1/4]
```

Direct sum.

### See also

qpp::dirsumpow()

Used to stop the recursion for the variadic template version of qpp::dirsum()

### **Parameters**

head	Eigen expression
ncau	Ligon capicosion

Its argument head

Direct sum.

See also

qpp::dirsumpow()

# **Parameters**

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

# Returns

Direct sum of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

```
6.1.3.35 dirsum() [3/4]
```

Direct sum.

See also

qpp::dirsumpow()

# **Parameters**

As std::vector of Eigen expressions

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Direct sum.

See also

qpp::dirsumpow()

#### **Parameters**

As std::initializer\_list of Eigen expressions, such as {A1, A2, ..., Ak}

#### Returns

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

# 6.1.3.37 dirsumpow()

Direct sum power.

See also

qpp::dirsum()

# **Parameters**

Α	Eigen expression
n	Non-negative integer

Direct sum of A with itself n times  $A^{\oplus n}$ , as a dynamic matrix over the same scalar field as A

Eigen expression ostream manipulator.

# **Parameters**

Α	Eigen expression
chop	Set to zero the elements smaller in absolute value than <i>chop</i>

#### Returns

Instance of qpp::internal::IOManipEigen

Complex number ostream manipulator.

# **Parameters**

Z	Complex number (or any other type implicitly cast-able to std::complex <double>)</double>
chop	Set to zero the elements smaller in absolute value than chop

# Returns

Instance of qpp::internal::IOManipEigen

```
6.1.3.40 disp() [3/5]

template<typename InputIterator >
internal::IOManipRange<InputIterator> qpp::disp (
```

```
InputIterator first,
InputIterator last,
const std::string & separator,
const std::string & start = "[",
const std::string & end = "]")
```

Range ostream manipulator.

#### **Parameters**

first	Iterator to the first element of the range
last	Iterator to the last element of the range
separator	Separator
start	Left marking
end	Right marking

#### Returns

Instance of qpp::internal::IOManipRange

```
6.1.3.41 disp() [4/5]
```

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

#### **Parameters**

С	Container
separator	Separator
start	Left marking
end	Right marking

# Returns

Instance of qpp::internal::IOManipRange

# **6.1.3.42** disp() [5/5]

```
template<typename PointerType >
internal::IOManipPointer<PointerType> qpp::disp (
```

```
const PointerType * p,
idx N,
const std::string & separator,
const std::string & start = "[",
const std::string & end = "]")
```

C-style pointer ostream manipulator.

#### **Parameters**

р	Pointer to the first element
N	Number of elements to be displayed
separator	Separator
start	Left marking
end	Right marking

#### Returns

Instance of qpp::internal::IOManipPointer

#### 6.1.3.43 egcd()

Extended greatest common divisor of two integers.

# See also

qpp::gcd()

#### **Parameters**

а	Integer
b	Integer

# Returns

Tuple of: 1. Integer m, 2. Integer n, and 3. Non-negative integer gcd(a,b) such that ma + nb = gcd(a,b)

### 6.1.3.44 eig()

Full eigen decomposition.

#### See also

qpp::heig()

#### **Parameters**

```
A Eigen expression
```

#### Returns

Pair of: 1. Eigenvalues of *A*, as a complex dynamic column vector, and 2. Eigenvectors of *A*, as columns of a complex dynamic matrix

# 6.1.3.45 entanglement() [1/2]

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

#### See also

```
qpp::entropy()
```

# **Parameters**

Α	Eigen expression
dims	Dimensions of the bi-partite system

#### Returns

Entanglement, with the logarithm in base 2

# **6.1.3.46** entanglement() [2/2]

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

# See also

qpp::entropy()

# **Parameters**

Α	Eigen expression
d	Subsystem dimensions

#### Returns

Entanglement, with the logarithm in base 2

# **6.1.3.47 entropy()** [1/2]

von-Neumann entropy of the density matrix A

#### **Parameters**

```
A Eigen expression
```

# Returns

von-Neumann entropy, with the logarithm in base 2

# **6.1.3.48** entropy() [2/2]

Shannon entropy of the probability distribution prob.

# **Parameters**

prob Real probability vector
------------------------------

#### Returns

Shannon entropy, with the logarithm in base 2

```
6.1.3.49 evals()
```

Eigenvalues.

See also

qpp::hevals()

#### **Parameters**

```
A Eigen expression
```

# Returns

Eigenvalues of A, as a complex dynamic column vector

# 6.1.3.50 evects()

Eigenvectors.

See also

qpp::hevects()

#### **Parameters**

```
A Eigen expression
```

# Returns

Eigenvectors of A, as columns of a complex dynamic matrix

# 6.1.3.51 expm()

Matrix exponential.

# **Parameters**

A Eigen expression

# Returns

Matrix exponential of A

# 6.1.3.52 factors()

Prime factor decomposition.

Note

Runs in  $\mathcal{O}(\sqrt{n})$  time complexity

#### **Parameters**

a Integer different from 0, 1 or -1

# Returns

Integer vector containing the factors

# 6.1.3.53 funm()

Functional calculus f(A)

# **Parameters**

Α	Eigen expression
f	Pointer-to-function from complex to complex

```
Returns
```

```
f(A)
```

Greatest common divisor of two integers.

See also

```
qpp::lcm()
```

#### **Parameters**

а	Integer
b	Integer

# Returns

Greatest common divisor of a and b

Greatest common divisor of a list of integers.

See also

```
qpp::lcm()
```

# **Parameters**

```
as List of integers
```

# Returns

Greatest common divisor of all numbers in as

### 6.1.3.56 gconcurrence()

G-concurrence of the bi-partite pure state A.

Note


Both local dimensions must be equal

Uses qpp::logdet() to avoid overflows

See also

qpp::logdet()

#### **Parameters**



### Returns

G-concurrence

```
6.1.3.57 grams() [1/3]
```

Gram-Schmidt orthogonalization.

# **Parameters**

```
As std::vector of Eigen expressions as column vectors
```

### Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

```
6.1.3.58 grams() [2/3]
```

Gram-Schmidt orthogonalization.

#### **Parameters**

```
As std::initializer_list of Eigen expressions as column vectors
```

#### Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

Gram-Schmidt orthogonalization.

#### **Parameters**

A Eigen expression, the input vectors are the columns of A

#### Returns

Gram-Schmidt vectors of the columns of A, as columns of a dynamic matrix over the same scalar field as A

#### 6.1.3.60 heig()

Full eigen decomposition of Hermitian expression.

# See also

qpp::eig()

#### **Parameters**

A Eigen expression

Pair of: 1. Eigenvalues of A, as a real dynamic column vector, and 2. Eigenvectors of A, as columns of a complex dynamic matrix

#### 6.1.3.61 hevals()

Hermitian eigenvalues.

See also

qpp::evals()

#### **Parameters**

A Eigen expression

# Returns

Eigenvalues of Hermitian A, as a real dynamic column vector

# 6.1.3.62 hevects()

Eigenvectors of Hermitian matrix.

See also

qpp::evects()

#### **Parameters**

A Eigen expression

### Returns

Eigenvectors of Hermitian matrix A, as columns of a complex matrix

### 6.1.3.63 inverse()

Inverse.

#### **Parameters**

```
A Eigen expression
```

#### Returns

Inverse of A, as a dynamic matrix over the same scalar field as A

# 6.1.3.64 invperm()

```
\label{eq:std:vector} $$ std::vector < idx > & perm ) $$ [inline] $$
```

Inverse permutation.

#### **Parameters**

perm Permut	ation
-------------	-------

### Returns

Inverse of the permutation perm

# **6.1.3.65** ip() [1/2]

Generalized inner product.

### **Parameters**

phi	hi Column vector Eigen expression	
psi	Column vector Eigen expression	
subsys	Subsystem indexes over which phi is defined	
dims	Dimensions of the multi-partite system	

Inner product  $\langle \phi_{subsys} | \psi \rangle$ , as a scalar or column vector over the remaining Hilbert space

#### Generalized inner product.

#### **Parameters**

phi	Column vector Eigen expression
psi	Column vector Eigen expression
subsys	Subsystem indexes over which phi is defined
d	Subsystem dimensions

# Returns

Inner product  $\langle \phi_{subsys} | \psi \rangle$  , as a scalar or column vector over the remaining Hilbert space

# 6.1.3.67 isprime()

Primality test based on the Miller-Rabin's algorithm.

# **Parameters**

p	Integer different from 0, 1 or -1
k	Number of iterations. The probability of a false positive is $2^{-k}$ .

#### Returns

True if the number is (most-likely) prime, false otherwise

#### 6.1.3.68 kraus2choi()

Choi matrix.

See also

qpp::choi2kraus()

Constructs the Choi matrix of the channel specified by the set of Kraus operators  $\mathit{Ks}$  in the standard operator basis  $\{|i\rangle\langle j|\}$  ordered in lexicographical order, i.e.  $|0\rangle\langle 0|, |0\rangle\langle 1|$  etc.

Note

The superoperator matrix S and the Choi matrix C are related by  $S_{ab,mn}=C_{ma,nb}$ 

#### **Parameters**

Ks Set of Kraus operators

#### Returns

Choi matrix

#### 6.1.3.69 kraus2super()

Superoperator matrix.

Constructs the superoperator matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis  $\{|i\rangle\langle j|\}$  ordered in lexicographical order, i.e.  $|0\rangle\langle 0|$ ,  $|0\rangle\langle 1|$  etc.

### **Parameters**

Ks Set of Kraus operators

# Returns

Superoperator matrix

Kronecker product.

See also

qpp::kronpow()

Used to stop the recursion for the variadic template version of <a href="app::kron()">app::kron()</a>

#### **Parameters**

head	Eigen expression
------	------------------

#### Returns

Its argument head

```
6.1.3.71 kron() [2/4]
```

Kronecker product.

See also

qpp::kronpow()

#### **Parameters**

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

#### Returns

Kronecker product of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

#### See also

qpp::kronpow()

#### **Parameters**

As std::vector of Eigen expressions

#### Returns

Kronecker product of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Kronecker product.

#### See also

qpp::kronpow()

# **Parameters**

As std::initializer\_list of Eigen expressions, such as {A1, A2, ..., Ak}

# Returns

Kronecker product of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

# 6.1.3.74 kronpow()

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::kronpow (
```

```
const Eigen::MatrixBase< Derived > & A, idx n)
```

Kronecker power.

See also

qpp::kron()

# **Parameters**

Α	Eigen expression
n	Non-negative integer

### Returns

Kronecker product of A with itself n times  $A^{\otimes n}$ , as a dynamic matrix over the same scalar field as A

Least common multiple of two integers.

See also

qpp::gcd()

# **Parameters**

а	Integer
b	Integer

### Returns

Least common multiple of a and b

Least common multiple of a list of integers.

See also

```
qpp::gcd()
```

#### **Parameters**

```
as List of integers
```

#### Returns

Least common multiple of all numbers in as

# 6.1.3.77 load()

Loads Eigen matrix from a binary file (internal format) in double precision.

#### See also

```
qpp::save()
```

The template parameter cannot be automatically deduced and must be explicitly provided, depending on the scalar field of the matrix that is being loaded.

# Example:

```
// loads a previously saved Eigen dynamic complex matrix from "input.bin" cmat mat = load<cmat>("input.bin");
```

#### **Parameters**

```
fname Output file name
```

#### 6.1.3.78 loadMATLAB() [1/2]

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

```
qpp::saveMATLAB()
```

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen ket
// from the MATLAB file "input.mat"
ket psi = loadMATLABket>("input.mat");
```

# **Template Parameters**

Derived	Complex Eigen type
---------	--------------------

#### **Parameters**

mat_file	MATALB .mat file	
var_name	Variable name in the .mat file representing the matrix to be loaded	]

#### Returns

Eigen dynamic matrix

# 6.1.3.79 loadMATLAB() [2/2]

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

```
qpp::saveMATLAB()
```

The template parameter cannot be automatically deduced and must be explicitly provided

### Example:

```
// loads a previously saved Eigen dynamic double matrix
// from the MATLAB file "input.mat"
dmat mat = loadMATLAB<dmat>("input.mat");
```

# **Template Parameters**

е
е

#### **Parameters**

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be loaded

# Returns

Eigen dynamic matrix

# 6.1.3.80 logdet()

Logarithm of the determinant.

Useful when the determinant overflows/underflows

#### **Parameters**

```
A Eigen expression
```

#### Returns

Logarithm of the determinant of A, as a scalar over the same scalar field as A

# 6.1.3.81 logm()

Matrix logarithm.

# **Parameters**

A Eigen expression

Matrix logarithm of A

Logarithmic negativity of the bi-partite mixed state A.

# **Parameters**

Α	Eigen expression
dims	Dimensions of the bi-partite system

#### Returns

Logarithmic negativity, with the logarithm in base 2

# **6.1.3.83** lognegativity() [2/2]

```
template<typename Derived >
double qpp::lognegativity (
          const Eigen::MatrixBase< Derived > & A,
          idx d = 2 )
```

Logarithmic negativity of the bi-partite mixed state A.

#### **Parameters**

Α	Eigen expression
d	Subsystem dimensions

### Returns

Logarithmic negativity, with the logarithm in base 2

# 6.1.3.84 marginalX()

Marginal distribution.

#### **Parameters**

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels	1
	the rows, Y labels the columns)	

#### Returns

Real vector consisting of the marginal distribution of X

# 6.1.3.85 marginalY()

Marginal distribution.

#### **Parameters**

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels	
	the rows, Y labels the columns)	

### Returns

Real vector consisting of the marginal distribution of Y

# **6.1.3.86** measure() [1/9]

Measures the state vector or density operator A using the set of Kraus operators Ks.

# **Parameters**

Α	Eigen expression
Ks	Set of Kraus operators

### Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

#### **6.1.3.87** measure() [2/9]

Measures the state vector or density matrix A using the set of Kraus operators Ks.

#### **Parameters**

Α	Eigen expression
Ks	Set of Kraus operators

# Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

#### **6.1.3.88** measure() [3/9]

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

### **Parameters**

Α	Eigen expression	
U	Unitary matrix whose columns represent the measurement basis vectors	

#### Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

# **6.1.3.89** measure() [4/9]

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

#### See also

```
qpp::measure_seq()
```

#### Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

#### **Parameters**

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

#### Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

#### **6.1.3.90** measure() [5/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

### See also

```
qpp::measure_seq()
```

#### Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

#### **Parameters**

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

#### See also

```
qpp::measure_seq()
```

#### Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

#### **Parameters**

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

#### Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

# **6.1.3.92** measure() [7/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

#### See also

```
qpp::measure_seq()
```

#### Note

The dimension of all Ks must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

#### **Parameters**

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

#### Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

#### **6.1.3.93** measure() [8/9]

Measures the part *target* of the multi-partite state vector or density matrix *A* in the orthonormal basis or rank-1 projectors specified by the columns of the matrix *V*.

## See also

```
qpp::measure_seq()
```

## Note

The dimension of V must match the dimension of target. The measurement is destructive, i.e. the measured subsystems are traced away.

Α	Eigen expression
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part *target* of the multi-partite state vector or density matrix *A* in the orthonormal basis or rank-1 projectors specified by the columns of the matrix *V*.

#### See also

```
qpp::measure_seq()
```

#### Note

The dimension of *V* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

## **Parameters**

Α	Eigen expression	
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors	
target	Subsystem indexes that are measured	
d	Subsystem dimensions	

## Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

#### See also

qpp::measure()

#### **Parameters**

Α	Eigen expression
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

#### Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

## See also

qpp::measure()

#### **Parameters**

Α	Eigen expression
target	Subsystem indexes that are measured
d	Subsystem dimensions

## Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Multi-partite qudit ket.

#### See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket  $|\text{mask}\rangle$ , where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

#### **Parameters**

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

#### Returns

Multi-partite qudit state vector, as a complex dynamic column vector

Multi-partite qudit ket.

## See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket  $|mask\rangle$ , all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

#### **Parameters**

mask	std::vector of non-negative integers
d	Subsystem dimensions

#### Returns

Multi-partite qudit state vector, as a complex dynamic column vector

## 6.1.3.99 modinv()

Modular inverse of a mod p.

#### See also

```
qpp::egcd()
```

## Note

a and p must be co-prime

## **Parameters**

а	Non-negative integer
р	Non-negative integer

## Returns

```
Modular inverse a^{-1} \mod p
```

## 6.1.3.100 modmul()

```
bigint qpp::modmul (
                bigint a,
                bigint b,
                bigint p ) [inline]
```

Modular multiplication without overflow.

Computes  $ab \bmod p$  without overflow

## **Parameters**

а	Integer
b	Integer
р	Positive integer

## Returns

 $ab \bmod p$  avoiding overflow

## 6.1.3.101 modpow()

```
bigint qpp::modpow (
          bigint a,
```

```
bigint n,
bigint p ) [inline]
```

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

Note

Uses qpp::modmul() that avoids overflows

Computes  $a^n \bmod p$ 

#### **Parameters**

а	Non-negative integer
n	Non-negative integer
р	Strictly positive integer

#### Returns

```
a^n \bmod p
```

const std::vector< idx > & dims ) [inline]

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket  $|mask\rangle$ , where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

## **Parameters**

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

## Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

Projector onto multi-partite qudit ket.

#### See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket  $|mask\rangle$ , all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

#### **Parameters**

mask	std::vector of non-negative integers
d	Subsystem dimensions

#### Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

## 6.1.3.104 multiidx2n()

Multi-index to non-negative integer index.

#### See also

```
qpp::n2multiidx()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

#### **Parameters**

midx	Multi-index
dims	Dimensions of the multi-partite system

#### Returns

Non-negative integer index

## 6.1.3.105 n2multiidx()

```
\label{eq:std::vector} $$ std::vector < idx > qpp::n2multiidx ($$ idx n,$$ const std::vector < idx > & dims ) [inline]
```

Non-negative integer index to multi-index.

#### See also

```
qpp::multiidx2n()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

#### **Parameters**

n	Non-negative integer index
dims	Dimensions of the multi-partite system

## Returns

Multi-index of the same size as dims

## 6.1.3.106 negativity() [1/2]

Negativity of the bi-partite mixed state A.

## **Parameters**

Α	Eigen expression
dims	Dimensions of the bi-partite system

## Returns

Negativity

## **6.1.3.107** negativity() [2/2]

```
template<typename Derived >
double qpp::negativity (
```

```
const Eigen::MatrixBase< Derived > & A, idx d = 2)
```

Negativity of the bi-partite mixed state A.

#### **Parameters**

Α	Eigen expression
d	Subsystem dimensions

## Returns

Negativity

## 6.1.3.108 norm()

Frobenius norm.

#### **Parameters**

```
A Eigen expression
```

## Returns

Frobenius norm of A

## 6.1.3.109 normalize()

Normalizes state vector (column or row vector) or density matrix.

#### **Parameters**

A Eigen expression

Normalized state vector or density matrix

```
6.1.3.110 omega()

cplx qpp::omega (
          idx D ) [inline]
```

D-th root of unity.

#### **Parameters**

D Non-negative integer

6.1.3.111 operator""" \_i()

## Returns

D-th root of unity  $\exp(2\pi i/D)$ 

User-defined literal for complex  $i = \sqrt{-1}$  (real overload)

#### Example:

```
cplx z = 4.5_i; // type of z is std::complex<double>
```

## 6.1.3.112 powm()

Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

## See also

```
qpp::spectralpowm()
```

Explicitly multiplies the matrix A with itself n times. By convention  $A^0 = I$ .

Α	Eigen expression
n	Non-negative integer

#### Returns

Matrix power  $A^n$ , as a dynamic matrix over the same scalar field as A

## 6.1.3.113 prj()

#### Projector.

Normalized projector onto state vector

#### **Parameters**

```
A Eigen expression
```

#### Returns

Projector onto the state vector A, or the matrix Zero if A has norm zero (i.e. smaller than qpp::eps), as a dynamic matrix over the same scalar field as A

## **6.1.3.114** prod() [1/3]

Element-wise product of A.

## **Parameters**

```
A Eigen expression
```

#### Returns

Element-wise product of A, as a scalar over the same scalar field as A

Element-wise product of an STL-like range.

#### **Parameters**

first	Iterator to the first element of the range
last	Iterator to the last element of the range

InputIterator last )

## Returns

Element-wise product of the range, as a scalar over the same scalar field as the range

Element-wise product of the elements of an STL-like container.

#### **Parameters**

```
c STL-like container
```

## Returns

Element-wise product of the elements of the container, as a scalar over the same scalar field as the container

## See also

Partial trace.

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

#### Returns

Partial trace  $Tr_{subsys}(\cdot)$  over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

# 

Partial trace.

#### See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

#### **Parameters**

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

#### Returns

Partial trace  $Tr_{subsys}(\cdot)$  over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

```
6.1.3.119 ptrace1() [1/2]
```

Partial trace.

#### See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

#### **Parameters**

Α	Eigen expression
dims	Dimensions of the bi-partite system

#### Returns

Partial trace  $Tr_A(\cdot)$  over the first subsytem A in a bi-partite system  $A\otimes B$ , as a dynamic matrix over the same scalar field as A

## 6.1.3.120 ptrace1() [2/2]

Partial trace.

#### See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

#### **Parameters**

Α	Eigen expression
d	Subsystem dimensions

#### Returns

Partial trace  $Tr_A(\cdot)$  over the first subsystem A in a bi-partite system  $A\otimes B$ , as a dynamic matrix over the same scalar field as A

## **6.1.3.121** ptrace2() [1/2]

Partial trace.

#### See also

```
qpp::ptrace1()
```

Partial trace over the second subsystem of bi-partite state vector or density matrix

#### **Parameters**

Α	Eigen expression
dims	Dimensions of the bi-partite system

#### Returns

Partial trace  $Tr_B(\cdot)$  over the second subsytem B in a bi-partite system  $A\otimes B$ , as a dynamic matrix over the same scalar field as A

## 6.1.3.122 ptrace2() [2/2]

Partial trace.

#### See also

qpp::ptrace1()

Partial trace over the second subsystem of bi-partite state vector or density matrix

#### **Parameters**

Α	Eigen expression
d	Subsystem dimensions

#### Returns

Partial trace  $Tr_B(\cdot)$  over the second subsytem B in a bi-partite system  $A\otimes B$ , as a dynamic matrix over the same scalar field as A

## **6.1.3.123** ptranspose() [1/2]

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::ptranspose (
```

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & target,
const std::vector< idx > & dims )
```

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

#### **Parameters**

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

#### Returns

Partial transpose  $(\cdot)^{T_{subsys}}$  over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

## 6.1.3.124 ptranspose() [2/2]

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

## **Parameters**

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

## Returns

Partial transpose  $(\cdot)^{T_{subsys}}$  over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

#### 6.1.3.125 QFT()

```
template<typename Derived >
dyn_col_vect<typename Derived::Scalar> qpp::QFT (
```

```
const Eigen::MatrixBase< Derived > & A, idx d = 2, bool swap = true)
```

Qudit quantum Fourier transform.

#### **Parameters**

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

#### Returns

Qudit quantum Fourier transform applied on A

## 6.1.3.126 qmutualinfo() [1/2]

Quantum mutual information between 2 subsystems of a composite system.

## **Parameters**

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
dims	Dimensions of the multi-partite system

#### Returns

Mutual information between the 2 subsystems

## 6.1.3.127 qmutualinfo() [2/2]

Quantum mutual information between 2 subsystems of a composite system.

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
d	Subsystem dimensions

## Returns

Mutual information between the 2 subsystems

Generates a random real number uniformly distributed in the interval [a, b)

## **Parameters**

a	ì	Beginning of the interval, belongs to it
b	)	End of the interval, does not belong to it

#### Returns

Random real number (double) uniformly distributed in the interval [a, b)

Generates a random big integer uniformly distributed in the interval [a, b].

## Note

To avoid ambiguity with double qpp::rand(double, double) cast at least one of the arguments to qpp::bigint

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

Random big integer uniformly distributed in the interval [a, b]

Generates a random matrix with entries uniformly distributed in the interval [a, b)

If complex, then both real and imaginary parts are uniformly distributed in [a, b)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED\_TYPE. It is specialized only for qpp::dmat and qpp::cmat

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

## Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries uniformly distributed in [-1,1)
dmat mat = rand<dmat>(3, 3, -1, 1);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

#### Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd,
// with entries (both real and imaginary) uniformly distributed in [-1,1)
cmat mat = rand<cmat>(3, 3, -1, 1);
```

## **Parameters**

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

#### Returns

Random complex matrix

#### 6.1.3.133 randH()

```
cmat qpp::randH (
    idx D = 2) [inline]
```

Generates a random Hermitian matrix.

#### **Parameters**

D Dimension of the Hilbert space

Random Hermitian matrix

## 6.1.3.134 randidx()

```
idx qpp::randidx (
        idx a = std::numeric_limits<idx>::min(),
        idx b = std::numeric_limits<idx>::max() ) [inline]
```

Generates a random index (idx) uniformly distributed in the interval [a, b].

#### **Parameters**

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

#### Returns

Random index (idx) uniformly distributed in the interval [a, b]

## 6.1.3.135 randket()

```
ket qpp::randket (
idx D = 2) [inline]
```

Generates a random normalized ket (pure state vector)

## **Parameters**

D Dimension of the Hilbert space

#### Returns

Random normalized ket

## 6.1.3.136 randkraus()

```
std::vector<cmat> qpp::randkraus (
    idx N,
    idx D = 2 ) [inline]
```

Generates a set of random Kraus operators.

Note

The set of Kraus operators satisfy the closure condition  $\sum_i K_i^\dagger K_i = I$ 

#### **Parameters**

N	Number of Kraus operators
D	Dimension of the Hilbert space

#### Returns

Set of N Kraus operators satisfying the closure condition

Generates a random matrix with entries normally distributed in N(mean, sigma)

If complex, then both real and imaginary parts are normally distributed in N(mean, sigma)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED\_TYPE. It is specialized only for qpp::dmat and qpp::cmat

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

## Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries normally distributed in N(0,2)
dmat mat = randn<dmat>(3, 3, 0, 2);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

#### Returns

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

## Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd, 
// with entries (both real and imaginary) normally distributed in N(0,2) cmat mat = randn<cmat>(3, 3, 0, 2);
```

#### **Parameters**

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

#### Returns

Random complex matrix

Generates a random real number (double) normally distributed in N(mean, sigma)

#### **Parameters**

mean	Mean
sigma	Standard deviation

#### Returns

Random real number normally distributed in N(mean, sigma)

## 6.1.3.141 randperm()

```
std::vector<idx> qpp::randperm (
    idx N ) [inline]
```

Generates a random uniformly distributed permutation.

Uses Knuth shuffle method (as implemented by std::shuffle), so that all permutations are equally probable

#### **Parameters**

```
N Size of the permutation
```

## Returns

Random permutation of size N

## 6.1.3.142 randprime()

```
bigint qpp::randprime (
          bigint a,
          bigint b,
          idx N = 1000 ) [inline]
```

Generates a random big prime uniformly distributed in the interval [a, b].

а	Beginning of the interval, belongs to it
b	End of the interval, belongs to it
N	Maximum number of candidates

Random big integer uniformly distributed in the interval [a, b]

## 6.1.3.143 randprob()

```
\label{eq:std::vector} $$ \std::vector<double> qpp::randprob ( idx N) [inline]
```

Generates a random probability vector uniformly distributed over the probability simplex.

#### **Parameters**

N Size of the probability vector

## Returns

Random probability vector

## 6.1.3.144 randrho()

```
cmat qpp::randrho (
    idx D = 2 ) [inline]
```

Generates a random density matrix.

#### **Parameters**

D Dimension of the Hilbert space

#### Returns

Random density matrix

## 6.1.3.145 randU()

```
cmat qpp::randU (
    idx D = 2) [inline]
```

Generates a random unitary matrix.

D Dimension of the Hilbert space

## Returns

Random unitary

## 6.1.3.146 randV()

Generates a random isometry matrix.

## **Parameters**

Din	Size of the input Hilbert space
Dout	Size of the output Hilbert space

#### Returns

Random isometry matrix

```
6.1.3.147 renyi() [1/2]
```

Renyi-  $\alpha$  entropy of the density matrix  ${\it A}$ , for  $\alpha \geq 0$ .

#### Note

When  $\alpha \to 1$  the Renyi entropy converges to the von-Neumann entropy, with the logarithm in base 2

Α	Eigen expression
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

Renyi-  $\alpha$  entropy, with the logarithm in base 2

Renyi-  $\alpha$  entropy of the probability distribution *prob*, for  $\alpha \geq 0$ .

## Note

When  $\alpha \to 1$  the Renyi entropy converges to the Shannon entropy, with the logarithm in base 2

#### **Parameters**

prob	Real probability vector
alpha	Non-negative real number, use qpp::infty for $\alpha=\infty$

#### Returns

Renyi-  $\alpha$  entropy, with the logarithm in base 2

## 6.1.3.149 reshape()

## Reshape.

Uses column-major order when reshaping (same as MATLAB)

Α	Eigen expression
rows	Number of rows of the reshaped matrix
cols	Number of columns of the reshaped matrix

Reshaped matrix with rows rows and cols columns, as a dynamic matrix over the same scalar field as A

#### 6.1.3.150 rho2bloch()

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

#### See also

qpp::bloch2rho()

#### Note

It is implicitly assumed that the density matrix is Hermitian

#### **Parameters**

A Eigen expression

## Returns

3-dimensional Bloch vector

## 6.1.3.151 rho2pure()

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

#### Note

No purity check is done, the input state A must have rank one, otherwise the function returns the first non-zero eigenvector of A

#### **Parameters**

A Eigen expression, assumed to be proportional to a projector onto a pure state, i.e. A is assumed to have rank one

The unique non-zero eigenvector of A (up to a phase), as a dynamic column vector over the same scalar field as A

## 6.1.3.152 save()

Saves Eigen expression to a binary file (internal format) in double precision.

#### See also

qpp::load()

#### **Parameters**

Α	Eigen expression
fname	Output file name

## **6.1.3.153** saveMATLAB() [1/2]

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

## See also

qpp::loadMATLAB()

## **Template Parameters**

Complex Eigen type

Α	Eigen expression over the complex field
---	---

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be saved
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details

## **6.1.3.154** saveMATLAB() [2/2]

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

#### See also

qpp::loadMATLAB()

## **Template Parameters**

Npn-complex	Eigen type
-------------	------------

#### **Parameters**

Α	Non-complex Eigen expression	
mat_file	MATALB .mat file	
var_name	Variable name in the .mat file representing the matrix to be saved	
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details	

## 6.1.3.155 schatten()

## Schatten matrix norm.

Α	Eigen expression
p	Real number, greater or equal to 1, use qpp::infty for $p=\infty$

Schatten-p matrix norm of A

Schmidt basis on Alice side.

#### **Parameters**

Α	Eigen expression
dims	Dimensions of the bi-partite system

## Returns

Unitary matrix  $\boldsymbol{U}$  whose columns represent the Schmidt basis vectors on Alice side.

# 

Schmidt basis on Alice side.

idx d = 2)

#### **Parameters**

Α	Eigen expression
d	Subsystem dimensions

#### Returns

Unitary matrix U whose columns represent the Schmidt basis vectors on Alice side.

# 6.1.3.158 schmidtB() [1/2] template<typename Derived > cmat qpp::schmidtB (

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & dims )
```

Schmidt basis on Bob side.

#### **Parameters**

Α	Eigen expression
dims	Dimensions of the bi-partite system

#### Returns

Unitary matrix  ${\cal V}$  whose columns represent the Schmidt basis vectors on Bob side.

# 

Schmidt basis on Bob side.

idx d = 2)

#### **Parameters**

Α	Eigen expression
d	Subsystem dimensions

## Returns

Unitary matrix  ${\cal V}$  whose columns represent the Schmidt basis vectors on Bob side.

## 

Schmidt coefficients of the bi-partite pure state A.

#### Note

The sum of the squares of the Schmidt coefficients equals 1

## See also

qpp::schmidtprobs()

Α	Eigen expression
dims	Dimensions of the bi-partite system

#### Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

## **6.1.3.161** schmidtcoeffs() [2/2]

Schmidt coefficients of the bi-partite pure state A.

#### Note

The sum of the squares of the Schmidt coefficients equals 1

#### See also

qpp::schmidtprobs()

#### **Parameters**

Α	Eigen expression
d	Subsystem dimensions

## Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

## **6.1.3.162** schmidtprobs() [1/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

#### See also

qpp::schmidtcoeffs()

#### **Parameters**

Α	Eigen expression
dims	Dimensions of the bi-partite system

#### Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

## 6.1.3.163 schmidtprobs() [2/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

## See also

qpp::schmidtcoeffs()

## **Parameters**

Α	Eigen expression
d	Subsystem dimensions

## Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

#### 6.1.3.164 sigma()

#### Standard deviation.

prob	Real probability vector representing the probability distribution of X
X	Real random variable values represented by an STL-like container

#### Returns

Standard deviation of X

## 6.1.3.165 sinm()

Matrix sin.

#### **Parameters**

A Eigen expression

## Returns

Matrix sine of A

## 6.1.3.166 spectralpowm()

Matrix power.

See also

qpp::powm()

Uses the spectral decomposition of  $\emph{A}$  to compute the matrix power. By convention  $\emph{A}^0 = \emph{I}$  .

Α	Eigen expression
Z	Complex number

Matrix power  $A^z$ 

## 6.1.3.167 sqrtm()

Matrix square root.

#### **Parameters**

```
A Eigen expression
```

#### Returns

Matrix square root of A

## **6.1.3.168 sum()** [1/3]

Element-wise sum of A.

#### **Parameters**

```
A Eigen expression
```

## Returns

Element-wise sum of A, as a scalar over the same scalar field as A

## **6.1.3.169 sum()** [2/3]

Element-wise sum of an STL-like range.

### **Parameters**

first	Iterator to the first element of the range
last	Iterator to the last element of the range

#### Returns

Element-wise sum of the range, as a scalar over the same scalar field as the range

Element-wise sum of the elements of an STL-like container.

#### **Parameters**

```
c STL-like container
```

## Returns

Element-wise sum of the elements of the container, as a scalar over the same scalar field as the container

## 6.1.3.171 super2choi()

Converts superoperator matrix to Choi matrix.

## See also

qpp::choi2super()

#### **Parameters**

A Superoperator matrix

#### Returns

Choi matrix

## 6.1.3.172 svals()

Singular values.

#### **Parameters**

A Eigen expression

#### Returns

Singular values of A, ordered in decreasing order, as a real dynamic column vector

#### 6.1.3.173 svd()

Full singular value decomposition.

## **Parameters**

A Eigen expression

## Returns

Tuple of: 1. Left sigular vectors of A, as columns of a complex dynamic matrix, 2. Singular values of A, ordered in decreasing order, as a real dynamic column vector, and 3. Right singular vectors of A, as columns of a complex dynamic matrix

## 6.1.3.174 svdU()

Left singular vectors.

#### **Parameters**

```
A Eigen expression
```

## Returns

Complex dynamic matrix, whose columns are the left singular vectors of A

### 6.1.3.175 svdV()

Right singular vectors.

## **Parameters**

```
A Eigen expression
```

## Returns

Complex dynamic matrix, whose columns are the right singular vectors of A

## 6.1.3.176 syspermute() [1/2]

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

## **Parameters**

Α	Eigen expression
perm	Permutation
dims	Dimensions of the multi-partite system

### Returns

Permuted system, as a dynamic matrix over the same scalar field as A

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

#### **Parameters**

Α	Eigen expression	
perm	Permutation	
d	Subsystem dimensions	

### Returns

Permuted system, as a dynamic matrix over the same scalar field as A

## 6.1.3.178 TFQ()

Inverse (adjoint) qudit quantum Fourier transform.

## **Parameters**

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

## Returns

Inverse (adjoint) qudit quantum Fourier transform applied on A

### 6.1.3.179 trace()

Trace.

**Parameters** 

```
A Eigen expression
```

### Returns

Trace of A, as a scalar over the same scalar field as A

## 6.1.3.180 transpose()

Transpose.

**Parameters** 

```
A Eigen expression
```

#### Returns

Transpose of A, as a dynamic matrix over the same scalar field as A

```
6.1.3.181 tsallis() [1/2] template<typename Derived > double qpp::tsallis ( const Eigen::MatrixBase< Derived > & A, double q)
```

Tsallis- q entropy of the density matrix A, for  $q \ge 0$ .

Note

When  $q \to 1$  the Tsallis entropy converges to the von-Neumann entropy, with the logarithm in base e

## **Parameters**

Α	Eigen expression
q	Non-negative real number

## Returns

Tsallis- q entropy

Tsallis- q entropy of the probability distribution *prob*, for  $q \ge 0$ .

### Note

When  $q \to 1$  the Tsallis entropy converges to the Shannon entropy, with the logarithm in base e

## **Parameters**

prob	Real probability vector
q	Non-negative real number

## Returns

Tsallis- q entropy

## 6.1.3.183 uniform()

```
std::vector<double> qpp::uniform (
    idx N ) [inline]
```

Uniform probability distribution vector.

## **Parameters**

N Size of the alphabet

### Returns

Real vector consisting of a uniform distribution of size N

## 6.1.3.184 var()

Variance.

### **Parameters**

prob	Real probability vector representing the probability distribution of $X$
Χ	Real random variable values represented by an STL-like container

#### Returns

Variance of X

## 6.1.3.185 x2contfrac()

Simple continued fraction expansion.

## See also

```
qpp::contfrac2x()
```

## **Parameters**

Χ	Real number
Ν	Maximum number of terms in the expansion
cut	Stop the expansion when the next term is greater than cut

## Returns

Integer vector containing the simple continued fraction expansion of x. If there are M less than N terms in the expansion, a shorter vector with M components is returned.

## 6.1.4 Variable Documentation

## 6.1.4.1 chop

```
constexpr double qpp::chop = 1e-10
```

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

### 6.1.4.2 ee

```
constexpr double qpp::ee = 2.718281828459045235360287471352662497
```

Base of natural logarithm, e.

#### 6.1.4.3 eps

```
constexpr double qpp::eps = std::numeric_limits<double>::epsilon()
```

Used to decide whether a number or expression in double precision is zero or not for the purpose of a specific computation.

## Example:

```
if(std::abs(x) < qpp::eps) // x is zero</pre>
```

### 6.1.4.4 idx\_infty

```
const idx qpp::idx_infty = static_cast<idx>(-1)
```

Used to denote the largest unsigned index.

## 6.1.4.5 infty

```
constexpr double qpp::infty = std::numeric_limits<double>::max()
```

Used to denote infinity in double precision.

#### 6.1.4.6 maxn

```
constexpr idx qpp::maxn = 64
```

Maximum number of allowed qubits/qudits (subsystems)

Used internally to allocate arrays on the stack (for performance reasons):

### 6.1.4.7 pi

```
constexpr double qpp::pi = 3.141592653589793238462643383279502884
```

 $\pi$ 

## 6.2 qpp::exception Namespace Reference

Quantum++ exception hierarchy namespace.

### Classes

• class CustomException

Custom exception.

· class DimsInvalid

Invalid dimension(s) exception.

· class DimsMismatchCvector

Dimension(s) mismatch column vector size exception.

• class DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

· class DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

· class DimsMismatchVector

Dimension(s) mismatch vector size exception.

class DimsNotEqual

Dimensions not equal exception.

· class Duplicates

System (e.g. std::vector) has duplicates exception.

class Exception

Base class for generating Quantum++ custom exceptions.

class InvalidIterator

Invalid iterator.

• class MatrixMismatchSubsys

Matrix mismatch subsystems exception.

• class MatrixNotCvector

Matrix is not a column vector exception.

class MatrixNotRvector

Matrix is not a row vector exception.

class MatrixNotSquare

Matrix is not square exception.

· class MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

class MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

· class MatrixNotSquareNorVector

Matrix is not square nor vector exception.

· class MatrixNotVector

Matrix is not a vector exception.

class NoCodeword

Codeword does not exist exception.

· class NotBipartite

Not bi-partite exception.

· class NotImplemented

Code not yet implemented.

class NotQubitCvector

Column vector is not 2 x 1 exception.

class NotQubitMatrix

Matrix is not 2 x 2 exception.

· class NotQubitRvector

Row vector is not 1 x 2 exception.

class NotQubitSubsys

Subsystems are not qubits exception.

class NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

class OutOfRange

Argument out of range exception.

class PermInvalid

Invalid permutation exception.

· class PermMismatchDims

Permutation mismatch dimensions exception.

class QuditAlreadyMeasured

Qudit was already measured exception.

· class SizeMismatch

Size mismatch exception.

• class SubsysMismatchDims

Subsystems mismatch dimensions exception.

class TypeMismatch

Type mismatch exception.

class UndefinedType

Not defined for this type exception.

• class Unknown

Unknown exception.

class ZeroSize

Object has zero size exception.

## 6.2.1 Detailed Description

Quantum++ exception hierarchy namespace.

## 6.3 qpp::experimental Namespace Reference

Experimental/test functions/classes, do not use or modify.

## 6.3.1 Detailed Description

Experimental/test functions/classes, do not use or modify.

## 6.4 qpp::internal Namespace Reference

Internal utility functions, do not use them directly or modify them.

### **Classes**

- struct Display Impl
- · class IOManipEigen
- · class IOManipPointer
- · class IOManipRange
- · class Singleton

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

## **Functions**

- void n2multiidx (idx n, idx numdims, const idx \*const dims, idx \*result) noexcept
- idx multiidx2n (const idx \*const midx, idx numdims, const idx \*const dims) noexcept
- $\bullet \ \ \text{template}{<} \text{typename Derived} >$

bool check\_square\_mat (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ \mathsf{template} \mathord{<} \mathsf{typename} \ \mathsf{Derived} >$ 

bool <a href="mailto:check\_vector">bool check\_vector</a> (const Eigen::MatrixBase</a> Derived > &A)

• template<typename Derived >

bool check\_rvector (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$ 

bool check\_cvector (const Eigen::MatrixBase< Derived > &A)

• template<typename T >

bool check\_nonzero\_size (const T &x) noexcept

- template<typename T1 , typename T2 >

bool check\_matching\_sizes (const T1 &lhs, const T2 &rhs) noexcept

- bool check\_dims (const std::vector< idx > &dims)
- template<typename Derived >

 $bool\ check\_dims\_match\_mat\ (const\ std::vector < idx > \&dims,\ const\ Eigen::MatrixBase < Derived > \&A)$ 

• template<typename Derived >

bool check\_dims\_match\_cvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool check dims match rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- bool check\_eq\_dims (const std::vector< idx > &dims, idx dim) noexcept
- bool check\_no\_duplicates (std::vector< idx > v)
- bool check\_subsys\_match\_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)

```
    template < typename Derived >
        bool check_qubit_matrix (const Eigen::MatrixBase < Derived > &A) noexcept
```

• template<typename Derived >

bool check\_qubit\_cvector (const Eigen::MatrixBase< Derived > &A) noexcept

template<typename Derived >
 bool check\_qubit\_rvector (const Eigen::MatrixBase< Derived > &A) noexcept

template<typename Derived >
 bool check\_qubit\_vector (const Eigen::MatrixBase< Derived > &A) noexcept

bool check\_perm (const std::vector< idx > &perm)

template<typename Derived1 , typename Derived2 >
 dyn\_mat< typename Derived1::Scalar > kron2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::
 MatrixBase< Derived2 > &B)

template<typename Derived1, typename Derived2 >
 dyn\_mat< typename Derived1::Scalar > dirsum2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen
 ::MatrixBase< Derived2 > &B)

template<typename T > void variadic\_vector\_emplace (std::vector< T > &)

- $\begin{tabular}{ll} & \textbf{template}$<&typename T$, typename First , typename... Args>&void variadic_vector_emplace (std::vector< T>&v, First &&first, Args &&... args) \\ \end{tabular}$
- idx get num subsys (idx D, idx d)
- idx get\_dim\_subsys (idx sz, idx N)

## 6.4.1 Detailed Description

Internal utility functions, do not use them directly or modify them.

## 6.4.2 Function Documentation

## 6.4.2.1 check\_cvector()

## 6.4.2.2 check\_dims()

```
bool qpp::internal::check_dims (  const \ std::vector < \ idx \ > \ \& \ dims \ ) \quad [inline]
```

### 6.4.2.3 check\_dims\_match\_cvect()

## 6.4.2.4 check\_dims\_match\_mat()

## 6.4.2.5 check\_dims\_match\_rvect()

## 6.4.2.6 check\_eq\_dims()

## 6.4.2.7 check\_matching\_sizes()

## 6.4.2.8 check\_no\_duplicates()

```
bool qpp::internal::check_no_duplicates ( {\tt std::vector} < {\tt idx} \, > \, v \; ) \quad [{\tt inline}]
```

```
6.4.2.9 check_nonzero_size()
template<typename T >
bool qpp::internal::check_nonzero_size (
            const T & x ) [noexcept]
6.4.2.10 check_perm()
bool qpp::internal::check_perm (
            const std::vector< idx > & perm ) [inline]
6.4.2.11 check_qubit_cvector()
template<typename Derived >
bool qpp::internal::check_qubit_cvector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.12 check_qubit_matrix()
template<typename Derived >
bool qpp::internal::check_qubit_matrix (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.13 check_qubit_rvector()
template<typename Derived >
bool qpp::internal::check_qubit_rvector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.14 check_qubit_vector()
template<typename Derived >
bool qpp::internal::check_qubit_vector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
```

```
6.4.2.15 check_rvector()
```

```
template<typename Derived >
bool qpp::internal::check_rvector (
            const Eigen::MatrixBase< Derived > & A )
6.4.2.16 check_square_mat()
template<typename Derived >
bool qpp::internal::check_square_mat (
            const Eigen::MatrixBase< Derived > & A )
6.4.2.17 check_subsys_match_dims()
bool qpp::internal::check_subsys_match_dims (
            const std::vector< idx > & subsys,
            const std::vector< idx > & dims ) [inline]
6.4.2.18 check_vector()
template<typename Derived >
bool qpp::internal::check_vector (
            const Eigen::MatrixBase< Derived > & A )
6.4.2.19 dirsum2()
template<typename Derived1 , typename Derived2 >
dyn_mat<typename Derived1::Scalar> qpp::internal::dirsum2 (
            const Eigen::MatrixBase< Derived1 > & A,
            const Eigen::MatrixBase< Derived2 > & B )
6.4.2.20 get_dim_subsys()
idx qpp::internal::get_dim_subsys (
            idx sz,
             idx N ) [inline]
```

### 6.4.2.21 get\_num\_subsys()

```
idx qpp::internal::get_num_subsys (
            idx D,
             idx d ) [inline]
6.4.2.22 kron2()
template<typename Derived1 , typename Derived2 >
dyn_mat<typename Derived1::Scalar> qpp::internal::kron2 (
            const Eigen::MatrixBase< Derived1 > & A,
             const Eigen::MatrixBase< Derived2 > & B )
6.4.2.23 multiidx2n()
idx qpp::internal::multiidx2n (
             const idx *const midx,
             idx numdims,
             const idx *const dims ) [inline], [noexcept]
6.4.2.24 n2multiidx()
void qpp::internal::n2multiidx (
             idx n,
             idx numdims,
             const idx *const dims,
             idx * result ) [inline], [noexcept]
6.4.2.25 variadic_vector_emplace() [1/2]
template<typename T >
void qpp::internal::variadic_vector_emplace (
            std::vector< T > & )
6.4.2.26 variadic_vector_emplace() [2/2]
template<typename T , typename First , typename... Args>
void qpp::internal::variadic_vector_emplace (
             std::vector< T > & v,
             First && first,
             Args &&... args )
```

## 6.5 qpp::literals Namespace Reference

## **Functions**

```
• constexpr cplx operator"" _i (unsigned long long int x) noexcept \textit{User-defined literal for complex } i = \sqrt{-1} \textit{ (integer overload)}
```

```
template<char... Bits>
ket operator"" _ket ()
```

Multi-partite qubit ket user-defined literal.

template<char... Bits> bra operator"" \_bra ()

Multi-partite qubit bra user-defined literal.

template<char... Bits> cmat operator"" \_prj ()

Multi-partite qubit projector user-defined literal.

## 6.5.1 Function Documentation

```
6.5.1.1 operator"""_bra()

template<char... Bits>
bra qpp::literals::operator"" _bra ( )
```

Multi-partite qubit bra user-defined literal.

See also

```
qpp::mket() and qpp::adjoint()
```

Constructs the multi-partite qubit bra  $\langle \mathrm{Bits}|$ 

**Template Parameters** 

```
Bits String of binary numbers representing the qubit bra
```

## Returns

Multi-partite qubit bra, as a complex dynamic row vector

User-defined literal for complex  $i = \sqrt{-1}$  (integer overload)

## Example:

```
cplx z = 4_i; // type of z is std::complex<double>
```

## 6.5.1.3 operator""" \_ket()

```
template<char... Bits>
ket qpp::literals::operator"" _ket ( )
```

Multi-partite qubit ket user-defined literal.

See also

qpp::mket()

Constructs the multi-partite qubit ket  $|Bits\rangle$ 

## **Template Parameters**

Bits	String of binary numbers representing the qubit ket
------	---

#### Returns

Multi-partite qubit ket, as a complex dynamic column vector

## 6.5.1.4 operator""" \_prj()

```
template<char... Bits>
cmat qpp::literals::operator"" _prj ( )
```

Multi-partite qubit projector user-defined literal.

See also

qpp::mprj()

Constructs the multi-partite qubit projector  $|\mathrm{Bits}\rangle\langle\mathrm{Bits}|$  (in the computational basis)

## **Template Parameters**

Bits String of binary numbers representing the qubit state to project on

$\mathbf{L}$	ΔT	 rn	c

Multi-partite qubit projector, as a complex dynamic matrix

# **Chapter 7**

# **Class Documentation**

# 7.1 qpp::Bit\_circuit Class Reference


Classical reversible circuit simulator.

#include <classes/reversible.h>

Inheritance diagram for qpp::Bit\_circuit:



Collaboration diagram for qpp::Bit\_circuit:



## Classes

struct Gate\_count

## **Public Member Functions**

- Bit\_circuit (const Dynamic\_bitset &dynamic\_bitset)
  - Conversion constructor, used to initialize a qpp::Bit\_circuit with a qpp::Dynamic\_bitset.
- Bit\_circuit & X (idx pos)

Bit flip.

Bit\_circuit & NOT (idx pos)

Bit flip

• Bit\_circuit & CNOT (const std::vector< idx > &pos)

Controlled-NOT.

• Bit\_circuit & TOF (const std::vector< idx > &pos)

Toffoli gate.

Bit\_circuit & SWAP (const std::vector < idx > &pos)

Swap bits.

• Bit\_circuit & FRED (const std::vector< idx > &pos)

Fredkin gate (Controlled-SWAP)

• Bit\_circuit & reset () noexcept

Reset the circuit all zero, clear all gates.

Dynamic\_bitset (idx N)

Inherited constructor.

## **Public Attributes**

struct qpp::Bit\_circuit::Gate\_count gate\_count
 Gate counters.

## **Additional Inherited Members**

## 7.1.1 Detailed Description

Classical reversible circuit simulator.

## 7.1.2 Constructor & Destructor Documentation

### 7.1.2.1 Bit\_circuit()

Conversion constructor, used to initialize a <a href="mailto:qpp::Bit\_circuit">qpp::Bit\_circuit</a> with a <a href="qpp::Dynamic\_bitset">qpp::Dynamic\_bitset</a>.

## **Parameters**

## 7.1.3 Member Function Documentation

### 7.1.3.1 CNOT()

Controlled-NOT.

## **Parameters**

```
pos Bit position in the circuit
```

## Returns

Reference to the current instance

## 7.1.3.2 Dynamic\_bitset()

```
qpp::Dynamic_bitset::Dynamic_bitset [inline], [explicit]
```

Inherited constructor.

## 7.1.3.3 FRED()

Fredkin gate (Controlled-SWAP)

**Parameters** 

pos Bit positions in the circuit, in the order control-target-target

## Returns

Reference to the current instance

## 7.1.3.4 NOT()

```
Bit_circuit& qpp::Bit_circuit::NOT (
        idx pos ) [inline]
```

Bit flip.

See also

qpp::Bit\_circuit::X()

## **Parameters**

pos Bit position in the circuit

## Returns

Reference to the current instance

## 7.1.3.5 reset()

```
Bit_circuit& qpp::Bit_circuit::reset ( ) [inline], [noexcept]
```

Reset the circuit all zero, clear all gates.

## Returns

Reference to the current instance

## 7.1.3.6 SWAP()

Swap bits.

### **Parameters**

pos Bit positions in the circuit

### Returns

Reference to the current instance

## 7.1.3.7 TOF()

Toffoli gate.

## **Parameters**

pos | Bit positions in the circuit, in the order control-control-target

## Returns

Reference to the current instance

## 7.1.3.8 X()

```
Bit_circuit& qpp::Bit_circuit::X (
        idx pos ) [inline]
```

Bit flip.

See also

qpp::Bit\_circuit::NOT()

#### **Parameters**

pos Bit position in the circuit

Returns

Reference to the current instance

## 7.1.4 Member Data Documentation

## 7.1.4.1 gate\_count

```
struct qpp::Bit_circuit::Gate_count qpp::Bit_circuit::gate_count
```

Gate counters.

The documentation for this class was generated from the following file:


• classes/reversible.h

## 7.2 qpp::Codes Class Reference


const Singleton class that defines quantum error correcting codes

```
#include <classes/codes.h>
```

Inheritance diagram for qpp::Codes:



Collaboration diagram for qpp::Codes:



## **Public Types**

• enum Type { Type::FIVE\_QUBIT = 1, Type::SEVEN\_QUBIT\_STEANE, Type::NINE\_QUBIT\_SHOR }

Code types, add more codes here if needed.

## **Public Member Functions**

ket codeword (Type type, idx i) const
 Returns the codeword of the specified code type.

## **Private Member Functions**

• Codes ()

Default constructor.

∼Codes ()=default

Default destructor.

## **Friends**

class internal::Singleton < const Codes >

## **Additional Inherited Members**

## 7.2.1 Detailed Description

const Singleton class that defines quantum error correcting codes

## 7.2.2 Member Enumeration Documentation

## 7.2.2.1 Type

```
enum qpp::Codes::Type [strong]
```

Code types, add more codes here if needed.

See also

```
qpp::Codes::codeword()
```

### Enumerator

FIVE_QUBIT	[[5,1,3]] qubit code
SEVEN_QUBIT_STEANE	[[7,1,3]] Steane qubit code
NINE_QUBIT_SHOR	[[9,1,3]] Shor qubit code

## 7.2.3 Constructor & Destructor Documentation

## 7.2.3.1 Codes()

```
qpp::Codes::Codes ( ) [inline], [private]
```

Default constructor.

## 7.2.3.2 ∼Codes()

```
qpp::Codes::~Codes ( ) [private], [default]
```

Default destructor.

## 7.2.4 Member Function Documentation

## 7.2.4.1 codeword()

Returns the codeword of the specified code type.

See also

qpp::Codes::Type

### **Parameters**

type	Code type
i	Codeword index

### Returns

i-th codeword of the code type

## 7.2.5 Friends And Related Function Documentation

## 7.2.5.1 internal::Singleton < const Codes >

```
friend class internal::Singleton< const Codes > [friend]
```

The documentation for this class was generated from the following file:

classes/codes.h

## 7.3 qpp::exception::CustomException Class Reference


Custom exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::CustomException:



Collaboration diagram for qpp::exception::CustomException:



## **Public Member Functions**

· CustomException (const std::string &where, const std::string &what)

## **Private Member Functions**

std::string type\_description () const override
 Exception type description.

## **Private Attributes**

std::string what\_{{}}

## 7.3.1 Detailed Description

Custom exception.

Custom exception, the user must provide a custom message

## 7.3.2 Constructor & Destructor Documentation

### 7.3.2.1 CustomException()

### 7.3.3 Member Function Documentation

### 7.3.3.1 type\_description()

```
std::string qpp::exception::CustomException::type_description ( ) const [inline], [override],
[private], [virtual]
```

Exception type description.

## Returns

**Exception** type description

Implements qpp::exception::Exception.

### 7.3.4 Member Data Documentation

## 7.3.4.1 what\_

```
std::string qpp::exception::CustomException::what_ {} [private]
```

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.4 qpp::exception::DimsInvalid Class Reference

Invalid dimension(s) exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsInvalid:



Collaboration diagram for qpp::exception::DimsInvalid:



## **Public Member Functions**

• std::string type\_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

## 7.4.1 Detailed Description

Invalid dimension(s) exception.

std::vector<idx> of dimensions has zero size or contains zeros

## 7.4.2 Member Function Documentation

## 7.4.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

where Text representing where the exception occurred

## 7.4.2.2 type\_description()

std::string qpp::exception::DimsInvalid::type\_description ( ) const [inline], [override],
[virtual]

Exception type description.

## Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.5 qpp::exception::DimsMismatchCvector Class Reference


Dimension(s) mismatch column vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchCvector:



Collaboration diagram for qpp::exception::DimsMismatchCvector:



## **Public Member Functions**

• std::string type\_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

## 7.5.1 Detailed Description

Dimension(s) mismatch column vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a column vector)

### 7.5.2 Member Function Documentation

## 7.5.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

## **Parameters**

where Text representing where the exception occurred
--

## 7.5.2.2 type\_description()

std::string qpp::exception::DimsMismatchCvector::type\_description ( ) const [inline], [override],
[virtual]

Exception type description.

## Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.6 qpp::exception::DimsMismatchMatrix Class Reference


Dimension(s) mismatch matrix size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchMatrix:



Collaboration diagram for qpp::exception::DimsMismatchMatrix:



## **Public Member Functions**

• std::string type\_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

# 7.6.1 Detailed Description

Dimension(s) mismatch matrix size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of rows of the Eigen::Matrix (assumed to be a square matrix)

#### 7.6.2 Member Function Documentation

#### 7.6.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where Text representing where the exception occurred
--

## 7.6.2.2 type\_description()

```
std::string qpp::exception::DimsMismatchMatrix::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

## Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

# 7.7 qpp::exception::DimsMismatchRvector Class Reference


Dimension(s) mismatch row vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchRvector:



Collaboration diagram for qpp::exception::DimsMismatchRvector:



# **Public Member Functions**

• std::string type\_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

# 7.7.1 Detailed Description

Dimension(s) mismatch row vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row vector)

#### 7.7.2 Member Function Documentation

### 7.7.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

Text representing where the exception of	d
--	---

## 7.7.2.2 type\_description()

std::string qpp::exception::DimsMismatchRvector::type\_description ( ) const [inline], [override],
[virtual]

Exception type description.

## Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

# 7.8 qpp::exception::DimsMismatchVector Class Reference

Dimension(s) mismatch vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchVector:



Collaboration diagram for qpp::exception::DimsMismatchVector:



## **Public Member Functions**

• std::string type\_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

# 7.8.1 Detailed Description

Dimension(s) mismatch vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row/column vector)

#### 7.8.2 Member Function Documentation

#### 7.8.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred
******	Toxt representing where the exception eccurred

## 7.8.2.2 type\_description()

```
std::string qpp::exception::DimsMismatchVector::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

## Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.9 qpp::exception::DimsNotEqual Class Reference


Dimensions not equal exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsNotEqual:



Collaboration diagram for qpp::exception::DimsNotEqual:



# **Public Member Functions**

• std::string type\_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

# 7.9.1 Detailed Description

Dimensions not equal exception.

Local/global dimensions are not equal

## 7.9.2 Member Function Documentation

# 7.9.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

where Text representing where the exception occurred

# 7.9.2.2 type\_description()

std::string qpp::exception::DimsNotEqual::type\_description ( ) const [inline], [override],
[virtual]

Exception type description.

#### Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

# 7.10 qpp::internal::Display\_Impl\_ Struct Reference

```
#include <internal/util.h>
```

Inheritance diagram for qpp::internal::Display\_Impl\_:



#### **Public Member Functions**

template<typename T >
 std::ostream & display\_impl\_ (const T &A, std::ostream &os, double chop=qpp::chop) const

# 7.10.1 Member Function Documentation

# 7.10.1.1 display\_impl\_()

The documentation for this struct was generated from the following file:


• internal/util.h

# 7.11 qpp::exception::Duplicates Class Reference


System (e.g. std::vector) has duplicates exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Duplicates:



Collaboration diagram for qpp::exception::Duplicates:



## **Public Member Functions**

• std::string type\_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

# 7.11.1 Detailed Description

System (e.g. std::vector) has duplicates exception.

#### 7.11.2 Member Function Documentation

## 7.11.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where Text representing where the exception occurred

## 7.11.2.2 type\_description()

```
std::string qpp::exception::Duplicates::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

### Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.12 qpp::Dynamic\_bitset Class Reference

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std:bitset < N >)

#include <classes/reversible.h>

Inheritance diagram for qpp::Dynamic\_bitset:



Collaboration diagram for qpp::Dynamic\_bitset:



# **Public Types**

- using value\_type = unsigned int
   Type of the storage elements.
- using storage\_type = std::vector< value\_type >
   Type of the storage.

#### **Public Member Functions**

• Dynamic bitset (idx N)

Constructor, initializes all bits to false (zero)

virtual ~Dynamic bitset ()=default

Default virtual destructor.

const storage\_type & data () const

Raw storage space of the bitset.

• idx size () const noexcept

Number of bits stored in the bitset.

• idx storage\_size () const noexcept

Size of the underlying storage space (in units of value\_type, unsigned int by default)

· idx count () const noexcept

Number of bits set to one in the bitset (Hamming weight)

bool get (idx pos) const noexcept

The value of the bit at position pos.

· bool none () const noexcept

Checks whether none of the bits are set.

• bool all () const noexcept

Checks whether all bits are set.

• bool any () const noexcept

Checks whether any bit is set.

Dynamic\_bitset & set (idx pos, bool value=true)

Sets the bit at position pos.

Dynamic\_bitset & set () noexcept

Set all bits to true.

• Dynamic bitset & rand (idx pos, double p=0.5)

Sets the bit at position pos according to a Bernoulli(p) distribution.

• Dynamic\_bitset & rand (double p=0.5)

Sets all bits according to a Bernoulli(p) distribution.

Dynamic\_bitset & reset (idx pos)

Sets the bit at position pos to false.

Dynamic\_bitset & reset () noexcept

Sets all bits to false.

Dynamic\_bitset & flip (idx pos)

Flips the bit at position pos.

· Dynamic bitset & flip () noexcept

Flips all bits.

• bool operator== (const Dynamic\_bitset &rhs) const noexcept

Equality operator.

• bool operator!= (const Dynamic\_bitset &rhs) const noexcept

Inequality operator.

• idx operator- (const Dynamic\_bitset &rhs) const noexcept

Number of places the two bitsets differ (Hamming distance)

template < class CharT = char, class Traits = std::char\_traits < CharT>, class Allocator = std::allocator < CharT>> std::basic\_string < CharT, Traits, Allocator > to\_string (CharT zero=CharT('0'), CharT one=CharT('1')) const String representation.

#### **Protected Member Functions**

- idx index\_ (idx pos) const
   Index of the pos bit in the storage space.
- idx offset\_ (idx pos) const

Offset of the pos bit in the storage space relative to its index.

# **Protected Attributes**

```
• idx storage_size_
Storage size.
```

idx N

Number of bits.

std::vector< value\_type > v\_
 Storage space.

#### **Private Member Functions**

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display()* override, displays the bitset bit by bit

#### 7.12.1 Detailed Description

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

## 7.12.2 Member Typedef Documentation

```
7.12.2.1 storage_type
```

```
using qpp::Dynamic_bitset::storage_type = std::vector<value_type>
```

Type of the storage.

# 7.12.2.2 value\_type

```
using qpp::Dynamic_bitset::value_type = unsigned int
```

Type of the storage elements.

## 7.12.3 Constructor & Destructor Documentation

## 7.12.3.1 Dynamic\_bitset()

Constructor, initializes all bits to false (zero)

#### **Parameters**

N Number of bits in the bitset

```
7.12.3.2 ~Dynamic_bitset()
```

```
virtual qpp::Dynamic_bitset::~Dynamic_bitset ( ) [virtual], [default]
```

Default virtual destructor.

## 7.12.4 Member Function Documentation

```
7.12.4.1 all()
```

```
bool qpp::Dynamic_bitset::all ( ) const [inline], [noexcept]
```

Checks whether all bits are set.

## Returns

True if all of the bits are set

## 7.12.4.2 any()

```
bool qpp::Dynamic_bitset::any ( ) const [inline], [noexcept]
```

Checks whether any bit is set.

#### Returns

True if any of the bits is set

# 7.12.4.3 count()

```
idx qpp::Dynamic_bitset::count ( ) const [inline], [noexcept]
```

Number of bits set to one in the bitset (Hamming weight)

#### Returns

Hamming weight

## 7.12.4.4 data()

```
const storage_type& qpp::Dynamic_bitset::data ( ) const [inline]
```

Raw storage space of the bitset.

## Returns

Const reference to the underlying storage space

## 7.12.4.5 display()

qpp::IDisplay::display() override, displays the bitset bit by bit

#### **Parameters**

os Output stream passed by reference

#### Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.12.4.6 flip() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip (
        idx pos ) [inline]
```

Flips the bit at position pos.

#### **Parameters**

pos Position in the bitset

#### Returns

Reference to the current instance

```
7.12.4.7 flip() [2/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::flip ( ) [inline], [noexcept]
```

Flips all bits.

#### Returns

Reference to the current instance

# 7.12.4.8 get()

```
bool qpp::Dynamic_bitset::get (
          idx pos ) const [inline], [noexcept]
```

The value of the bit at position pos.

#### **Parameters**

pos	Position in the bitset
-----	------------------------

## Returns

The value of the bit at position pos

# 7.12.4.9 index\_()

Index of the pos bit in the storage space.

## **Parameters**

```
pos Bit location
```

## Returns

Index of the pos bit in the storage space

#### 7.12.4.10 none()

```
bool qpp::Dynamic_bitset::none ( ) const [inline], [noexcept]
```

Checks whether none of the bits are set.

#### Returns

True if none of the bits are set

## 7.12.4.11 offset\_()

Offset of the *pos* bit in the storage space relative to its index.

#### **Parameters**

```
pos Bit location
```

## Returns

Offset of the pos bit in the storage space relative to its index

#### 7.12.4.12 operator"!=()

Inequality operator.

#### **Parameters**

```
rhs Dynamic_bitset against which the inequality is being tested
```

#### Returns

True if the bitsets are not equal (bit by bit), false otherwise

## 7.12.4.13 operator-()

Number of places the two bitsets differ (Hamming distance)

## **Parameters**

```
rhs Dynamic_bitset against which the Hamming distance is computed
```

## Returns

Hamming distance

## 7.12.4.14 operator==()

Equality operator.

#### **Parameters**

```
rhs Dynamic_bitset against which the equality is being tested
```

#### Returns

True if the bitsets are equal (bit by bit), false otherwise

## **7.12.4.15** rand() [1/2]

```
Dynamic_bitset& qpp::Dynamic_bitset::rand (
    idx pos,
    double p = 0.5 ) [inline]
```

Sets the bit at position *pos* according to a Bernoulli(p) distribution.

## **Parameters**

pos	Position in the bitset
р	Probability

#### Returns

Reference to the current instance

Sets all bits according to a Bernoulli(p) distribution.

#### **Parameters**

```
p Probability
```

#### **Returns**

Reference to the current instance

Sets the bit at position pos to false.

#### **Parameters**

```
pos Position in the bitset
```

### Returns

Reference to the current instance

```
7.12.4.18 reset() [2/2]
Dynamic_bitset& qpp::Dynamic_bitset::reset ( ) [inline], [noexcept]
Sets all bits to false.
```

## Returns

Reference to the current instance

```
7.12.4.19 set() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::set (
        idx pos,
        bool value = true ) [inline]
```

Sets the bit at position pos.

## **Parameters**

pos	Position in the bitset
value	Bit value

# Returns

Reference to the current instance

```
7.12.4.20 set() [2/2]
Dynamic_bitset& qpp::Dynamic_bitset::set ( ) [inline], [noexcept]
```

Set all bits to true.

## Returns

Reference to the current instance

```
7.12.4.21 size()
```

```
idx qpp::Dynamic_bitset::size ( ) const [inline], [noexcept]
```

Number of bits stored in the bitset.

## Returns

Number of bits stored in the bitset

```
7.12.4.22 storage_size()
```

```
idx qpp::Dynamic_bitset::storage_size ( ) const [inline], [noexcept]
```

Size of the underlying storage space (in units of value\_type, unsigned int by default)

#### Returns

Size of the underlying storage space

## 7.12.4.23 to\_string()

## String representation.

## **Template Parameters**

CharT	String character type
Traits	String traits
Allocator	String Allocator

#### **Parameters**

	Character representing the zero
one	Character representing the one

#### Returns

The bitset as a string

#### 7.12.5 Member Data Documentation

```
7.12.5.1 N_
```

```
idx qpp::Dynamic_bitset::N_ [protected]
```

Number of bits.


# 7.12.5.2 storage\_size\_

```
idx qpp::Dynamic_bitset::storage_size_ [protected]
```

# Storage size.

166	Class Documentation
7.12.5.3 v_	
<pre>std::vector<value_type> qpp::Dynamic_bitset::v_ [protected]</value_type></pre>	
Storage space.	
The documentation for this class was generated from the following file:	
• classes/reversible.h	
7.13 qpp::exception::Exception Class Reference	
Base class for generating Quantum++ custom exceptions.	
<pre>#include <classes exception.h=""></classes></pre>	

Inheritance diagram for qpp::exception::Exception:



Collaboration diagram for qpp::exception::Exception:



## **Public Member Functions**

• Exception (const std::string &where)

Constructs an exception.

- virtual const char \* what () const noexcept override

Overrides std::exception::what()

• virtual std::string type\_description () const =0

Exception type description.

## **Private Attributes**

- std::string where\_
- std::string msg\_

# 7.13.1 Detailed Description

Base class for generating Quantum++ custom exceptions.

Derive from this class if more exceptions are needed, making sure to override qpp::exception::Exception::type\_description() in the derived class and to inherit the constructor qpp::exception::Exception::Exception(). Preferably keep your newly defined exception classes in the namespace qpp::exception.

Example:

### 7.13.2 Constructor & Destructor Documentation

## 7.13.2.1 Exception()

Constructs an exception.

#### **Parameters**

where Text representing where the exception occurred

### 7.13.3 Member Function Documentation

#### 7.13.3.1 type\_description()

```
std::string qpp::exception::Exception::type_description ( ) const [inline], [pure virtual]
```

Exception type description.

### Returns

#### **Exception** type description

Implemented in qpp::exception::InvalidIterator, qpp::exception::NotImplemented, qpp::exception::CustomException, qpp::exception::Duplicates, qpp::exception::QuditAlreadyMeasured, qpp::exception::UndefinedType, qpp::exception::SizeMismatch, qpp::exception::TypeMismatch, qpp::exception::OutOfRange, qpp::exception::NotOdeword, qpp::exception::NotBipartite, qpp::exception::NotQubitSubsys, qpp::exception::NotQubitVector, qpp::exception::NotQubitRvector, qpp::exception::NotQubitCvector qpp::exception::NotQubitMatrix, qpp::exception::PermMismatchDims, qpp::exception::PermInvalid, qpp::exception::SubsysMismatchEqpp::exception::DimsMismatchVector, qpp::exception::DimsMismatchCvector, qpp::exception::DimsMismatchMatrix, qpp::exception::DimsNotEqual, qpp::exception::DimsInvalid, qpp::exception::MatrixMismatchSu qpp::exception::MatrixNotSquareNorVector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::Unknown.

## 7.13.3.2 what()

virtual const char\* qpp::exception::Exception::what ( ) const [inline], [override], [virtual],
[noexcept]

Overrides std::exception::what()

#### Returns

**Exception** description

#### 7.13.4 Member Data Documentation

```
7.13.4.1 msg_
```

std::string qpp::exception::Exception::msg\_ [mutable], [private]

## 7.13.4.2 where\_

std::string qpp::exception::Exception::where\_ [private]

The documentation for this class was generated from the following file:

· classes/exception.h

# 7.14 qpp::Bit\_circuit::Gate\_count Struct Reference

```
#include <classes/reversible.h>
```

## **Public Attributes**

- idx NOT = 0
- idx & X = NOT
- idx CNOT = 0
- idx SWAP = 0
- idx FRED = 0
- idx TOF = 0

## 7.14.1 Member Data Documentation

# 7.14.1.1 CNOT

```
idx qpp::Bit_circuit::Gate_count::CNOT = 0
```

#### 7.14.1.2 FRED

```
idx qpp::Bit_circuit::Gate_count::FRED = 0
```

# 7.14.1.3 NOT

```
idx qpp::Bit_circuit::Gate_count::NOT = 0
```

# 7.14.1.4 SWAP

```
idx qpp::Bit_circuit::Gate_count::SWAP = 0
```

# 7.14.1.5 TOF

```
idx qpp::Bit_circuit::Gate_count::TOF = 0
```

## 7.14.1.6 X

```
idx& qpp::Bit_circuit::Gate_count::X = NOT
```

The documentation for this struct was generated from the following file:

• classes/reversible.h

# 7.15 qpp::Gates Class Reference


const Singleton class that implements most commonly used gates

#include <classes/gates.h>

Inheritance diagram for qpp::Gates:



Collaboration diagram for qpp::Gates:



## **Public Member Functions**

- cmat Rn (double theta, const std::vector< double > &n) const
   Qubit rotation of theta about the 3-dimensional real (unit) vector n.
- cmat RX (double theta) const

Qubit rotation of theta about the X axis.

• cmat RY (double theta) const

Qubit rotation of theta about the Y axis.

cmat RZ (double theta) const

Qubit rotation of theta about the Z axis.

• cmat Zd (idx D=2) const

Generalized Z gate for qudits.

```
• cmat SWAPd (idx D=2) const
          SWAP gate for qudits.
    • cmat Fd (idx D=2) const
          Quantum Fourier transform gate for qudits.

    cmat MODMUL (idx a, idx N, idx n) const

          Modular multiplication gate for qubits Implements |x\rangle \longrightarrow |ax \bmod N\rangle.

    cmat Xd (idx D=2) const

          Generalized X gate for qudits.
    • template<typename Derived = Eigen::MatrixXcd>
      Derived Id (idx D=2) const
          Identity gate.

    template<typename Derived >

      dyn mat< typename Derived::Scalar > CTRL (const Eigen::MatrixBase< Derived > &A, const std::vector<
      idx > &ctrl, const std::vector < idx > &target, idx n, idx d=2) const
          Generates the multi-partite multiple-controlled-A gate in matrix form.

    template<typename Derived >

      dyn mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
      std::vector < idx > &dims) const
          Expands out.

    template<typename Derived >

      dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
      std::initializer list< idx > &dims) const
          Expands out.

    template<typename Derived >

      dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, idx n,
      idx d=2) const
          Expands out.
    • std::string get_name (const cmat &U) const
          Get the name of the most common qubit gates.
Public Attributes
    cmat Id2 {cmat::Identity(2, 2)}
          Identity gate.

    cmat H {cmat::Zero(2, 2)}

          Hadamard gate.
    cmat X {cmat::Zero(2, 2)}
          Pauli Sigma-X gate.

    cmat Y {cmat::Zero(2, 2)}

          Pauli Sigma-Y gate.

    cmat Z {cmat::Zero(2, 2)}

          Pauli Sigma-Z gate.

    cmat S {cmat::Zero(2, 2)}

          S gate.

    cmat T {cmat::Zero(2, 2)}

          T gate.

    cmat CNOT {cmat::Identity(4, 4)}

          Controlled-NOT control target gate.

    cmat CZ {cmat::Identity(4, 4)}

          Controlled-Phase gate.

    cmat CNOTba {cmat::Zero(4, 4)}
```

```
Controlled-NOT target->control gate.
```

• cmat SWAP {cmat::Identity(4, 4)}

SWAP gate.

• cmat TOF {cmat::ldentity(8, 8)}

Toffoli gate.

• cmat FRED {cmat::ldentity(8, 8)}

Fredkin gate.

## **Private Member Functions**

• Gates ()

Initializes the gates.

∼Gates ()=default

Default destructor.

#### **Friends**

class internal::Singleton < const Gates >

# **Additional Inherited Members**

# 7.15.1 Detailed Description

const Singleton class that implements most commonly used gates

# 7.15.2 Constructor & Destructor Documentation

```
7.15.2.1 Gates()
```

```
qpp::Gates::Gates ( ) [inline], [private]
```

Initializes the gates.

# 7.15.2.2 $\sim$ Gates()

```
qpp::Gates::\sim Gates ( ) [private], [default]
```

Default destructor.

## 7.15.3 Member Function Documentation

## 7.15.3.1 CTRL()

Generates the multi-partite multiple-controlled-A gate in matrix form.

#### See also

```
qpp::applyCTRL()
```

#### Note

The dimension of the gate A must match the dimension of target

#### **Parameters**

Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
n	Total number of subsystems
d	Subsystem dimensions

#### Returns

CTRL-A gate, as a matrix over the same scalar field as A

## **7.15.3.2 expandout()** [1/3]

## Expands out.

#### See also

```
qpp::kron()
```

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

#### **Parameters**

	Α	Eigen expression
	pos	Position
ĺ	dims	Dimensions of the multi-partite system

#### Returns

Tensor product  $I\otimes\cdots\otimes I\otimes A\otimes I\otimes\cdots\otimes I$ , with A on position pos, as a dynamic matrix over the same scalar field as A

```
7.15.3.3 expandout() [2/3]
```

#### Expands out.

#### See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

#### Note

The std::initializer\_list overload exists because otherwise, in the degenerate case when *dims* has only one element, the one element list is implicitly converted to the element's underlying type, i.e. qpp::idx, which has the net effect of picking the wrong (non-vector) qpp::expandout() overload

## Parameters

Α	Eigen expression
pos	Position
dims	Dimensions of the multi-partite system

### Returns

Tensor product  $I\otimes\cdots\otimes I\otimes A\otimes I\otimes\cdots\otimes I$ , with A on position pos, as a dynamic matrix over the same scalar field as A

#### 7.15.3.4 expandout() [3/3]

Expands out.

#### See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

#### **Parameters**

Α	Eigen expression
pos	Position
n	Number of subsystems
d	Subsystem dimensions

#### Returns

Tensor product  $I \otimes \cdots \otimes I \otimes A \otimes I \otimes \cdots \otimes I$ , with A on position pos, as a dynamic matrix over the same scalar field as A

## 7.15.3.5 Fd()

```
cmat qpp::Gates::Fd (
    idx D = 2 ) const [inline]
```

Quantum Fourier transform gate for qudits.

Note

Defined as 
$$F = \sum_{j,k=0}^{D-1} \exp(2\pi \mathrm{i} jk/D) |j\rangle\langle k|$$

### **Parameters**

D Dimension of the Hilbert space

## Returns

Fourier transform gate for qudits

#### 7.15.3.6 get\_name()

Get the name of the most common qubit gates.

Note

Assumes that the gate U is represented by a square matrix. If not, returns the empty string

#### **Parameters**

U | Complex matrix representing the quantum gate

#### Returns

The name of the gate (if any), otherwise the empty string

# 7.15.3.7 ld()

```
template<typename Derived = Eigen::MatrixXcd>
Derived qpp::Gates::Id (
    idx D = 2 ) const [inline]
```

Identity gate.

Note

Can change the return type from complex matrix (default) by explicitly specifying the template parameter

## Parameters

D Dimension of the Hilbert space

## Returns

Identity gate on a Hilbert space of dimension D

# 7.15.3.8 MODMUL()

```
cmat qpp::Gates::MODMUL (
    idx a,
```

```
idx N, idx n) const [inline]
```

Modular multiplication gate for qubits Implements  $|x\rangle \longrightarrow |ax \bmod N\rangle$ .

Note

For the gate to be unitary, *a* and *N* should be co-prime. The function does not check co-primality in release versions!

The number of qubits required to implement the gate should satisfy  $n \geq \lceil \log_2(N) \rceil$ 

#### **Parameters**

а	Positive integer less than N
Ν	Positive integer
n	Number of qubits required for implementing the gate

#### Returns

Modular multiplication gate

## 7.15.3.9 Rn()

Qubit rotation of *theta* about the 3-dimensional real (unit) vector *n*.

## **Parameters**

theta	Rotation angle
n	3-dimensional real (unit) vector

#### Returns

Rotation gate

## 7.15.3.10 RX()

Qubit rotation of theta about the X axis.

## **Parameters**

theta	Rotation angle
-------	----------------

## Returns

Rotation gate

# 7.15.3.11 RY()

Qubit rotation of *theta* about the Y axis.

#### **Parameters**

## Returns

Rotation gate

# 7.15.3.12 RZ()

Qubit rotation of theta about the Z axis.

#### **Parameters**

```
theta Rotation angle
```

## Returns

Rotation gate

# 7.15.3.13 SWAPd()

```
cmat qpp::Gates::SWAPd (
        idx D = 2 ) const [inline]
```

SWAP gate for qudits.

#### **Parameters**

D Dimension of the Hilbert space

## Returns

SWAP gate for qudits

## 7.15.3.14 Xd()

```
cmat qpp::Gates::Xd (
    idx D = 2 ) const [inline]
```

Generalized X gate for qudits.

Note

```
Defined as X=\sum_{j=0}^{D-1}|j\oplus 1\rangle\langle j|, i.e. raising operator X|j\rangle=|j\oplus 1\rangle
```

#### **Parameters**

D Dimension of the Hilbert space

# Returns

Generalized X gate for qudits

# 7.15.3.15 Zd()

```
cmat qpp::Gates::Zd (
    idx D = 2 ) const [inline]
```

Generalized Z gate for qudits.

Note

Defined as 
$$Z = \sum_{j=0}^{D-1} \exp(2\pi \mathrm{i} j/D) |j\rangle\langle j|$$

#### **Parameters**

D Dimension of the Hilbert space

Returns

Generalized Z gate for qudits

## 7.15.4 Friends And Related Function Documentation

```
7.15.4.1 internal::Singleton < const Gates >
friend class internal::Singleton < const Gates > [friend]
```

### 7.15.5 Member Data Documentation

```
7.15.5.1 CNOT
```

```
cmat qpp::Gates::CNOT {cmat::Identity(4, 4)}
```

Controlled-NOT control target gate.

#### 7.15.5.2 CNOTba

```
cmat qpp::Gates::CNOTba {cmat::Zero(4, 4)}
```

Controlled-NOT target->control gate.

# 7.15.5.3 CZ

```
cmat qpp::Gates::CZ {cmat::Identity(4, 4)}
```

Controlled-Phase gate.

## 7.15.5.4 FRED

```
cmat qpp::Gates::FRED {cmat::Identity(8, 8)}
```

Fredkin gate.

```
7.15.5.5 H
cmat qpp::Gates::H {cmat::Zero(2, 2)}
Hadamard gate.
7.15.5.6 ld2
cmat qpp::Gates::Id2 {cmat::Identity(2, 2)}
Identity gate.
7.15.5.7 S
cmat qpp::Gates::S {cmat::Zero(2, 2)}
S gate.
7.15.5.8 SWAP
cmat qpp::Gates::SWAP {cmat::Identity(4, 4)}
SWAP gate.
7.15.5.9 T
cmat qpp::Gates::T {cmat::Zero(2, 2)}
T gate.
7.15.5.10 TOF
cmat qpp::Gates::TOF {cmat::Identity(8, 8)}
Toffoli gate.
```

## 7.15.5.11 X

```
cmat qpp::Gates::X {cmat::Zero(2, 2)}
```

Pauli Sigma-X gate.

#### 7.15.5.12 Y

```
cmat qpp::Gates::Y {cmat::Zero(2, 2)}
```

Pauli Sigma-Y gate.

## 7.15.5.13 Z

```
cmat qpp::Gates::Z {cmat::Zero(2, 2)}
```

Pauli Sigma-Z gate.

The documentation for this class was generated from the following file:


· classes/gates.h

# 7.16 qpp::QCircuit::GateStep Struct Reference

One step consisting only of gates/operators in the circuit.

```
#include <classes/circuits.h>
```

Collaboration diagram for qpp::QCircuit::GateStep:



## **Public Member Functions**

• GateStep ()=default

Default constructor.

GateStep (GateType gate\_type, const cmat &gate, const std::vector< idx > &ctrl, const std::vector< idx > &target, std::string name="")

Constructs a gate step instance.

# **Public Attributes**

```
    GateType gate_type_ = GateType::NONE
        gate type
    cmat gate_
        gate
    std::vector < idx > ctrl_
        control
    std::vector < idx > target_
        target where the gate is applied
    std::string name_
        custom name of the step
```

## 7.16.1 Detailed Description

7.16.2.1 GateStep() [1/2]

One step consisting only of gates/operators in the circuit.

#### 7.16.2 Constructor & Destructor Documentation

Constructs a gate step instance.

## **Parameters**

gate_type	Gate type
gate	Quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes
step_no	Circuit step number
name	Optional gate name

## 7.16.3 Member Data Documentation

```
7.16.3.1 ctrl_
std::vector<idx> qpp::QCircuit::GateStep::ctrl_
control
7.16.3.2 gate_
cmat qpp::QCircuit::GateStep::gate_
gate
7.16.3.3 gate_type_
GateType qpp::QCircuit::GateStep::gate_type_ = GateType::NONE
gate type
7.16.3.4 name_
std::string qpp::QCircuit::GateStep::name_
```

custom name of the step

#### 7.16.3.5 target\_

```
std::vector<idx> qpp::QCircuit::GateStep::target_
```

target where the gate is applied

The documentation for this struct was generated from the following file:


· classes/circuits.h

# 7.17 qpp::IDisplay Class Reference

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

```
#include <classes/idisplay.h>
```

Inheritance diagram for qpp::IDisplay:



## **Public Member Functions**

- IDisplay ()=default
  - Default constructor.
- IDisplay (const IDisplay &)=default
  - Default copy constructor.
- IDisplay (IDisplay &&)=default

Default move constructor.

IDisplay & operator= (const IDisplay &)=default

Default copy assignment operator.

• IDisplay & operator= (IDisplay &&)=default

Default move assignment operator.

virtual ∼IDisplay ()=default

Default virtual destructor.

## **Private Member Functions**

virtual std::ostream & display (std::ostream &os) const =0
 Must be overridden by all derived classes.

#### **Friends**

std::ostream & operator<< (std::ostream &os, const IDisplay &rhs)</li>
 Overloads the extraction operator.

## 7.17.1 Detailed Description

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

This class defines friend inline std::ostream& operator<< (std::ostream& os, const qpp::IDisplay& rhs). The latter delegates the work to the pure private virtual function qpp::IDisplay::display() which has to be overridden by all derived classes.

#### 7.17.2 Constructor & Destructor Documentation

```
7.17.2.1 | Display() [1/3]

qpp::IDisplay::IDisplay ( ) [default]

Default constructor.
```

Default copy constructor.

Default move constructor.

```
7.17.2.4 \simIDisplay()
```

```
virtual qpp::IDisplay::~IDisplay ( ) [virtual], [default]
```

Default virtual destructor.

#### 7.17.3 Member Function Documentation

```
7.17.3.1 display()
```

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

 $\label{local-problem} \begin{array}{llll} \textbf{Implemented} & \textbf{in} & \textbf{qpp::QEngine,} & \textbf{qpp::QCircuit,} & \textbf{qpp::QCircuit::iterator::value\_type\_,} & \textbf{qpp::Dynamic\_bitset,} \\ \textbf{qpp::internal::IOManipEigen,} & \textbf{qpp::Timer} < \textbf{T, CLOCK\_T} >, & \textbf{qpp::internal::IOManipPointer} < \textbf{PointerType} >, & \textbf{and} \\ \textbf{qpp::internal::IOManipRange} < \textbf{InputIterator} >. \end{array}$ 

```
7.17.3.2 operator=() [1/2]
```

Default copy assignment operator.

```
7.17.3.3 operator=() [2/2]
```

Default move assignment operator.

#### 7.17.4 Friends And Related Function Documentation

#### 7.17.4.1 operator <<

```
std::ostream& operator<< (
          std::ostream & os,
          const IDisplay & rhs ) [friend]</pre>
```

Overloads the extraction operator.

Delegates the work to the virtual function <a href="mailto:qpp::IDisplay::display">qpp::IDisplay::display()</a>

The documentation for this class was generated from the following file:


· classes/idisplay.h

# 7.18 qpp::IJSON Class Reference

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

```
#include <classes/idisplay.h>
```

Inheritance diagram for qpp::IJSON:



## **Public Member Functions**

• IJSON ()=default

Default constructor.

• IJSON (const IJSON &)=default

Default copy constructor.

• IJSON (IJSON &&)=default

Default move constructor.

• IJSON & operator= (const IJSON &)=default

Default copy assignment operator.

• IJSON & operator= (IJSON &&)=default

Default move assignment operator.

virtual ∼IJSON ()=default

Default virtual destructor.

virtual std::string to\_JSON (bool enclosed\_in\_curly\_brackets=true) const =0

JSON representation of the derived instance, must be overridden by all derived classes.

# 7.18.1 Detailed Description

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

## 7.18.2 Constructor & Destructor Documentation

Default constructor.

Default copy constructor.

Default move constructor.

```
7.18.2.4 \simIJSON() virtual qpp::IJSON::\simIJSON ( ) [virtual], [default]
```

Default virtual destructor.

# 7.18.3 Member Function Documentation

Default copy assignment operator.

Default move assignment operator.

JSON representation of the derived instance, must be overridden by all derived classes.

**Parameters** 

Implemented in qpp::QEngine, and qpp::QCircuit.

The documentation for this class was generated from the following file:


· classes/idisplay.h

# 7.19 qpp::Init Class Reference


const Singleton class that performs additional initializations/cleanups

```
#include <classes/init.h>
```

Inheritance diagram for qpp::Init:



Collaboration diagram for qpp::Init:



# **Private Member Functions**

- Init ()
  - Additional initializations.
- ∼Init ()

Cleanups.

# **Friends**

class internal::Singleton < const Init >

## **Additional Inherited Members**

# 7.19.1 Detailed Description

const Singleton class that performs additional initializations/cleanups

## 7.19.2 Constructor & Destructor Documentation

```
7.19.2.1 Init()

qpp::Init::Init ( ) [inline], [private]

Additional initializations.
```

```
7.19.2.2 ~ Init()

qpp::Init::~Init ( ) [inline], [private]
```

Cleanups.

### 7.19.3 Friends And Related Function Documentation

```
7.19.3.1 internal::Singleton < const Init >
friend class internal::Singleton < const Init > [friend]
```

The documentation for this class was generated from the following file:


• classes/init.h

# 7.20 qpp::exception::InvalidIterator Class Reference


Invalid iterator.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::InvalidIterator:



Collaboration diagram for qpp::exception::InvalidIterator:



# **Public Member Functions**

• std::string type\_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

# 7.20.1 Detailed Description

Invalid iterator.

## 7.20.2 Member Function Documentation

## 7.20.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred
-------	--

# 7.20.2.2 type\_description()

std::string qpp::exception::InvalidIterator::type\_description ( ) const [inline], [override],
[virtual]

Exception type description.

### Returns

**Exception** type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

• classes/exception.h


# 7.21 qpp::internal::IOManipEigen Class Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipEigen:



Collaboration diagram for qpp::internal::IOManipEigen:



## **Public Member Functions**

- template<typename Derived > IOManipEigen (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
- IOManipEigen (const cplx z, double chop=qpp::chop)

# **Private Member Functions**

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

# **Private Attributes**

- cmat A\_
- double chop\_

#### 7.21.1 Constructor & Destructor Documentation

#### 7.21.2 Member Function Documentation

```
7.21.2.1 display()
```

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

### 7.21.3 Member Data Documentation

```
7.21.3.1 A_
```

```
cmat qpp::internal::IOManipEigen::A_ [private]
```

7.21.3.2 chop\_

double qpp::internal::IOManipEigen::chop\_ [private]


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


# 7.22 qpp::internal::IOManipPointer< PointerType > Class Template Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipPointer< PointerType >:



Collaboration diagram for qpp::internal::IOManipPointer< PointerType >:



#### **Public Member Functions**

- IOManipPointer (const PointerType \*p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")
- IOManipPointer (const IOManipPointer &)=default
- IOManipPointer & operator= (const IOManipPointer &)=default

#### **Private Member Functions**

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

## **Private Attributes**

- const PointerType \* p\_
- idx N\_
- std::string separator\_
- std::string start
- std::string end\_

#### 7.22.1 Constructor & Destructor Documentation

# **7.22.1.1 IOManipPointer()** [1/2]

## 7.22.1.2 IOManipPointer() [2/2]

#### 7.22.2 Member Function Documentation

#### 7.22.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

## 7.22.2.2 operator=()

#### 7.22.3 Member Data Documentation

```
7.22.3.1 end_
```

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::end_ [private]
```

### 7.22.3.2 N\_

```
template<typename PointerType>
idx qpp::internal::IOManipPointer< PointerType >::N_ [private]
```

# 7.22.3.3 p\_

```
template<typename PointerType>
const PointerType* qpp::internal::IOManipPointer< PointerType >::p_ [private]
```

#### 7.22.3.4 separator\_

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::separator_ [private]
```

#### 7.22.3.5 start

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::start_ [private]
```


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


# 7.23 qpp::internal::IOManipRange < InputIterator > Class Template Reference

```
#include <internal/classes/iomanip.h>
```

Inheritance diagram for qpp::internal::IOManipRange< InputIterator >:



Collaboration diagram for qpp::internal::IOManipRange< InputIterator >:



# **Public Member Functions**

- IOManipRange (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")
- IOManipRange (const IOManipRange &)=default
- IOManipRange & operator= (const IOManipRange &)=default

## **Private Member Functions**

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

## **Private Attributes**

- InputIterator first\_
- InputIterator last\_
- std::string separator\_
- std::string start\_
- std::string end\_

## 7.23.1 Constructor & Destructor Documentation

#### 7.23.1.1 IOManipRange() [1/2]

#### 7.23.1.2 IOManipRange() [2/2]

#### 7.23.2 Member Function Documentation

## 7.23.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

### 7.23.2.2 operator=()

#### 7.23.3 Member Data Documentation

```
7.23.3.1 end_
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::end_ [private]
7.23.3.2 first_
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::first_ [private]
7.23.3.3 last_
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::last_ [private]
7.23.3.4 separator_
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::separator_ [private]
```

```
7.23.3.5 start_
```

```
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::start_ [private]
```

The documentation for this class was generated from the following file:

• internal/classes/iomanip.h

# 7.24 qpp::is\_complex< T > Struct Template Reference


Checks whether the type is a complex type.

#include <traits.h>

Inheritance diagram for qpp::is\_complex< T >:



Collaboration diagram for qpp::is\_complex< T >:



## 7.24.1 Detailed Description

template<typename T> struct qpp::is\_complex< T>

Checks whether the type is a complex type.

Provides the constant member *value* which is equal to *true*, if the type is a complex type, i.e. *std::complex<T>* 

The documentation for this struct was generated from the following file:

# 7.25 qpp::is\_complex < std::complex < T > > Struct Template Reference


Checks whether the type is a complex number type, specialization for complex types.

```
#include <traits.h>
```

Inheritance diagram for qpp::is\_complex < std::complex < T > :



Collaboration diagram for qpp::is\_complex< std::complex< T >>:



# 7.25.1 Detailed Description

```
template<typename T> struct qpp::is_complex< std::complex< T > >
```

Checks whether the type is a complex number type, specialization for complex types.


The documentation for this struct was generated from the following file:

# 7.26 qpp::is\_iterable < T, typename > Struct Template Reference


Checks whether T is compatible with an STL-like iterable container.

#include <traits.h>

Inheritance diagram for qpp::is\_iterable < T, typename >:



Collaboration diagram for qpp::is\_iterable < T, typename >:



# 7.26.1 Detailed Description

template<typename T, typename = void> struct qpp::is\_iterable< T, typename >

Checks whether T is compatible with an STL-like iterable container.

Provides the constant member *value* which is equal to *true*, if *T* is compatible with an iterable container, i.e. provides at least *begin()* and *end()* member functions and allows de-referencing. Otherwise, *value* is equal to *false*.


The documentation for this struct was generated from the following file:

7.27 qpp::is\_iterable < T, to\_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().begin())) > Struct Template Reference

Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

```
#include <traits.h>
```

Inheritance diagram for qpp::is\_iterable < T, to\_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(\*(std::declval < T >().begin())) > :



Collaboration diagram for qpp::is\_iterable< T, to\_void< decltype(std::declval< T >().begin()), decltype(std:: $\leftarrow$  :declval< T >().end()), decltype(\*(std::declval< T >().begin()))>>:



## 7.27.1 Detailed Description

 $template < typename \ T > \\ struct \ qpp::is\_iterable < T, \ to\_void < decltype(std::declval < T > ().begin()), \ decltype(std::declval < T > ().end()), \ decltype(*(std::declval < T > ().begin())) > \\ ::declval < T > ().begin())) > \\$ 

Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

The documentation for this struct was generated from the following file:

· traits.h

# 7.28 qpp::is\_matrix\_expression < Derived > Struct Template Reference


Checks whether the type is an Eigen matrix expression.

```
#include <traits.h>
```

Inheritance diagram for qpp::is\_matrix\_expression< Derived >:



Collaboration diagram for qpp::is\_matrix\_expression< Derived >:



## 7.28.1 Detailed Description

template < typename Derived > struct qpp::is\_matrix\_expression < Derived >

Checks whether the type is an Eigen matrix expression.

Provides the constant member *value* which is equal to *true*, if the type is an Eigen matrix expression of type *Eigen* :: *MatrixBase* < *Derived* >. Otherwise, *value* is equal to *false*.


The documentation for this struct was generated from the following file:

# 7.29 qpp::QCircuit::iterator Class Reference

Quantum circuit bound-checking (safe) iterator.

#include <classes/circuits.h>

Collaboration diagram for qpp::QCircuit::iterator:



## Classes

class value\_type\_

# **Public Types**

• using difference\_type = long long

iterator trait

• using value\_type = value\_type\_

iterator trait

using pointer = const value\_type \*

iterator trait

• using reference = const value\_type &

iterator trait

• using iterator\_category = std::forward\_iterator\_tag

iterator trait

# **Public Member Functions**

• iterator ()=default

Default constructor.

• iterator (const iterator &)=default

Default copy constructor.

iterator & operator= (const iterator &)=default

Default copy assignment operator.

• iterator & operator++ ()

Prefix increment operator.

• iterator operator++ (int)

Postfix increment operator.

• bool operator== (const iterator &rhs) const

Equality operator.

- bool operator!= (iterator rhs) const Inequality operator.
- const value\_type\_ & operator\* () const

Safe de-referencing operator.

void set\_begin\_ (const QCircuit \*qcd)

Sets the iterator to std::begin(this)

void set\_end\_ (const QCircuit \*qcd)

Sets the iterator to std::begin(this)

## **Private Attributes**

```
    const QCircuit * qcd_ {nullptr}
    < non-owning pointer to const quantum circuit</li>
```

value\_type\_ elem\_ {nullptr}

# 7.29.1 Detailed Description

Quantum circuit bound-checking (safe) iterator.

Note

The iterator is a const\_iterator by default

# 7.29.2 Member Typedef Documentation

```
7.29.2.1 difference_type
```

```
using qpp::QCircuit::iterator::difference_type = long long
```

iterator trait

# 7.29.2.2 iterator\_category

```
using qpp::QCircuit::iterator::iterator_category = std::forward_iterator_tag
```

iterator trait

```
7.29.2.3 pointer
```

```
using qpp::QCircuit::iterator::pointer = const value_type*
```

iterator trait

## 7.29.2.4 reference

```
using qpp::QCircuit::iterator::reference = const value_type&
```

iterator trait

# 7.29.2.5 value\_type

```
using qpp::QCircuit::iterator::value_type = value_type_
```

iterator trait

# 7.29.3 Constructor & Destructor Documentation

```
7.29.3.1 iterator() [1/2]
```

```
qpp::QCircuit::iterator::iterator ( ) [default]
```

Default constructor.

```
7.29.3.2 iterator() [2/2]
```

Default copy constructor.

## 7.29.4 Member Function Documentation

# 7.29.4.1 operator"!=()

Inequality operator.

#### **Parameters**

rhs | Iterator against which the inequality is being tested

#### Returns

True if the iterators are not equal (bit by bit), false otherwise

## 7.29.4.2 operator\*()

```
const value_type_& qpp::QCircuit::iterator::operator* ( ) const [inline]
```

Safe de-referencing operator.

## Returns

Constant reference to the iterator element

# 7.29.4.3 operator++() [1/2]

```
iterator& qpp::QCircuit::iterator::operator++ ( ) [inline]
```

Prefix increment operator.

## Returns

Reference to the current instance

# 7.29.4.4 operator++() [2/2]

Postfix increment operator.

#### Returns

Copy of the current instance before the increment

```
7.29.4.5 operator=()
```

Default copy assignment operator.

Returns

Reference to the current instance

```
7.29.4.6 operator==()
```

Equality operator.

**Parameters** 

rhs | Iterator against which the equality is being tested

Returns

True if the iterators are equal, false otherwise

```
7.29.4.7 set_begin_()
```

Sets the iterator to std::begin(this)

**Parameters** 

qcd | Constant pointer to a quantum circuit

```
7.29.4.8 set_end_()
```

Sets the iterator to std::begin(this)

#### **Parameters**

qcd Constant pointer to a quantum circuit

#### 7.29.5 Member Data Documentation

```
7.29.5.1 elem_
value_type_ qpp::QCircuit::iterator::elem_ {nullptr} [private]

7.29.5.2 qcd_
const QCircuit* qpp::QCircuit::iterator::qcd_ {nullptr} [private]
```

The documentation for this class was generated from the following file:

· classes/circuits.h

# 7.30 qpp::make\_void < Ts > Struct Template Reference

Helper for <a href="mailto:qpp::to\_void">qpp::to\_void<>> alias template.</a>

< non-owning pointer to const quantum circuit

```
#include <traits.h>
```

# **Public Types**

• typedef void type

## 7.30.1 Detailed Description

```
template<typename... Ts>
struct qpp::make_void< Ts>
```

Helper for <a href="mailto:qpp::to\_void">qpp::to\_void<>> alias template.</a>

See also

qpp::to\_void<>

# 7.30.2 Member Typedef Documentation

# 7.30.2.1 type

```
template<typename... Ts>
typedef void qpp::make_void< Ts >::type
```

The documentation for this struct was generated from the following file:


• traits.h

# 7.31 qpp::exception::MatrixMismatchSubsys Class Reference


Matrix mismatch subsystems exception.

```
#include <classes/exception.h>
```

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Mismatch Subsys:$ 



Collaboration diagram for qpp::exception::MatrixMismatchSubsys:



## **Public Member Functions**

- std::string type\_description () const override
  - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

# 7.31.1 Detailed Description

Matrix mismatch subsystems exception.

Matrix size mismatch subsystem sizes (e.g. in qpp::apply())

# 7.31.2 Member Function Documentation

# 7.31.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

#### **Parameters**

where	Text representing where the exception occurred
-------	--

## 7.31.2.2 type\_description()

std::string qpp::exception::MatrixMismatchSubsys::type\_description ( ) const [inline], [override],
[virtual]

Exception type description.

#### Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.32 qpp::exception::MatrixNotCvector Class Reference


Matrix is not a column vector exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Cvector:$ 



Collaboration diagram for qpp::exception::MatrixNotCvector:



## **Public Member Functions**

- std::string type\_description () const override
  - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

# 7.32.1 Detailed Description

Matrix is not a column vector exception.

Eigen::Matrix is not a column vector

# 7.32.2 Member Function Documentation

# 7.32.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

#### **Parameters**

where	Text representing where the exception occurred
-------	--

## 7.32.2.2 type\_description()

std::string qpp::exception::MatrixNotCvector::type\_description ( ) const [inline], [override],
[virtual]

Exception type description.

#### Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.33 qpp::exception::MatrixNotRvector Class Reference


Matrix is not a row vector exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Rvector:$ 



Collaboration diagram for qpp::exception::MatrixNotRvector:



## **Public Member Functions**

- std::string type\_description () const override
  - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

# 7.33.1 Detailed Description

Matrix is not a row vector exception.

Eigen::Matrix is not a row vector

# 7.33.2 Member Function Documentation

# 7.33.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

#### **Parameters**

where	Text representing where the exception occurred
-------	--

## 7.33.2.2 type\_description()

std::string qpp::exception::MatrixNotRvector::type\_description ( ) const [inline], [override],
[virtual]

Exception type description.

#### Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.34 qpp::exception::MatrixNotSquare Class Reference


Matrix is not square exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception::MatrixNotSquare:$ 



 $Collaboration\ diagram\ for\ qpp::exception::MatrixNotSquare:$ 



## **Public Member Functions**

- std::string type\_description () const override
  - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

# 7.34.1 Detailed Description

Matrix is not square exception.

Eigen::Matrix is not a square matrix

# 7.34.2 Member Function Documentation

# 7.34.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

#### **Parameters**

where Text representing where the exception occurred
--

## 7.34.2.2 type\_description()

std::string qpp::exception::MatrixNotSquare::type\_description ( ) const [inline], [override],
[virtual]

Exception type description.

#### Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.35 qpp::exception::MatrixNotSquareNorCvector Class Reference


Matrix is not square nor column vector exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Square Nor Cvector:$ 



Collaboration diagram for qpp::exception::MatrixNotSquareNorCvector:



## **Public Member Functions**

- std::string type\_description () const override
  - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

# 7.35.1 Detailed Description

Matrix is not square nor column vector exception.

Eigen::Matrix is not a square matrix nor a column vector

# 7.35.2 Member Function Documentation

# 7.35.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

#### **Parameters**

where Text representing where the exception occ
---

## 7.35.2.2 type\_description()

std::string qpp::exception::MatrixNotSquareNorCvector::type\_description ( ) const [inline],
[override], [virtual]

Exception type description.

#### Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.36 qpp::exception::MatrixNotSquareNorRvector Class Reference


Matrix is not square nor row vector exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Square Nor Rvector:$ 



Collaboration diagram for qpp::exception::MatrixNotSquareNorRvector:



## **Public Member Functions**

- std::string type\_description () const override
  - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

# 7.36.1 Detailed Description

Matrix is not square nor row vector exception.

Eigen::Matrix is not a square matrix nor a row vector

# 7.36.2 Member Function Documentation

# 7.36.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

#### **Parameters**

where	Text representing where the exception occurred	1
-------	--	---

## 7.36.2.2 type\_description()

```
std::string qpp::exception::MatrixNotSquareNorRvector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

#### Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.37 qpp::exception::MatrixNotSquareNorVector Class Reference


Matrix is not square nor vector exception.

```
#include <classes/exception.h>
```

 $Inheritance\ diagram\ for\ qpp::exception:: Matrix Not Square Nor Vector:$ 



Collaboration diagram for qpp::exception::MatrixNotSquareNorVector:



## **Public Member Functions**

- std::string type\_description () const override
  - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

# 7.37.1 Detailed Description

Matrix is not square nor vector exception.

Eigen::Matrix is not a square matrix nor a row/column vector

# 7.37.2 Member Function Documentation

# 7.37.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

#### **Parameters**

where	Text representing where the exception occurred
-------	--

## 7.37.2.2 type\_description()

std::string qpp::exception::MatrixNotSquareNorVector::type\_description ( ) const [inline],
[override], [virtual]

Exception type description.

#### Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.38 qpp::exception::MatrixNotVector Class Reference


Matrix is not a vector exception.

#include <classes/exception.h>

 $Inheritance\ diagram\ for\ qpp::exception::MatrixNotVector:$ 



Collaboration diagram for qpp::exception::MatrixNotVector:



## **Public Member Functions**

- std::string type\_description () const override
  - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

# 7.38.1 Detailed Description

Matrix is not a vector exception.

Eigen::Matrix is not a row or column vector

# 7.38.2 Member Function Documentation

# 7.38.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

#### **Parameters**

where	Text representing where the exception occurred	1
-------	--	---

# 7.38.2.2 type\_description()

std::string qpp::exception::MatrixNotVector::type\_description ( ) const [inline], [override],
[virtual]

Exception type description.

#### **Returns**

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.39 qpp::QCircuit::MeasureStep Struct Reference

One step consisting only of measurements in the circuit.

```
#include <classes/circuits.h>
```

Collaboration diagram for qpp::QCircuit::MeasureStep:



#### **Public Member Functions**

• MeasureStep ()=default

Default constructor.

MeasureStep (MeasureType measurement\_type, const std::vector < cmat > &mats, const std::vector < idx > &target, idx c\_reg, std::string name="")

Constructs a measurement step instance.

## **Public Attributes**

MeasureType measurement\_type\_ = MeasureType::NONE

measurement type

- std::vector< cmat > mats
- std::vector < idx > target\_

target where the measurement is applied

- idx c\_reg\_ {}
- · std::string name\_

custom name of the step

## 7.39.1 Detailed Description

One step consisting only of measurements in the circuit.

## 7.39.2 Constructor & Destructor Documentation

```
7.39.2.1 MeasureStep() [1/2]

qpp::QCircuit::MeasureStep::MeasureStep ( ) [default]
```

Default constructor.

## 7.39.2.2 MeasureStep() [2/2]

Constructs a measurement step instance.

#### **Parameters**

measurement_type	Measurement type
mats	Vector of measurement matrices (can be only one or many for Kraus measurements)
target	Target qudit indexes
c_reg	Classical register where the value of the measurement is stored
step_no	Circuit step number
name	Optional gate name

## 7.39.3 Member Data Documentation

```
7.39.3.1 c_reg_
```

```
idx qpp::QCircuit::MeasureStep::c_reg_ {}
```

index of the classical register where the measurement result is being stored

```
7.39.3.2 mats_
```

```
std::vector<cmat> qpp::QCircuit::MeasureStep::mats_
```

matrix/matrices that specify the measurement

## 7.39.3.3 measurement\_type\_

```
MeasureType qpp::QCircuit::MeasureStep::measurement_type_ = MeasureType::NONE
```

measurement type

```
7.39.3.4 name_
```

```
std::string qpp::QCircuit::MeasureStep::name_
```

custom name of the step

7.39.3.5 target\_

```
std::vector<idx> qpp::QCircuit::MeasureStep::target_
```

target where the measurement is applied

The documentation for this struct was generated from the following file:


· classes/circuits.h

# 7.40 qpp::exception::NoCodeword Class Reference


Codeword does not exist exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::NoCodeword:



Collaboration diagram for qpp::exception::NoCodeword:



## **Public Member Functions**

- std::string type\_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

# 7.40.1 Detailed Description

Codeword does not exist exception.

Codeword does not exist, thrown when calling qpp::Codes::codeword() with an invalid index

## 7.40.2 Member Function Documentation

#### 7.40.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

#### **Parameters**

where	Text representing where the exception occurred	1
-------	--	---

# 7.40.2.2 type\_description()

```
std::string qpp::exception::NoCodeword::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

#### Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.41 qpp::NoiseBase < T > Class Template Reference

Base class for all noise models, derive your particular noise model.

```
#include <classes/noise.h>
```

Collaboration diagram for qpp::NoiseBase< T >:



# **Public Types**

using noise\_type = T

#### **Public Member Functions**

• template<typename U = noise\_type>

NoiseBase (const std::vector< cmat > &Ks, typename std::enable\_if< std::is\_same< NoiseType::StateDependent, U >::value >::type \*=nullptr)

Constructs a noise instance for StateDependent noise type.

• template<typename U = noise\_type>

NoiseBase (const std::vector< cmat > &Ks, const std::vector< double > &probs, typename std::enable\_if< std::is same< NoiseType::StateIndependent, U >::value >::type \*=nullptr)

Constructs a noise instance for StateIndependent noise type.

virtual ∼NoiseBase ()=default

Default virtual destructor.

idx get\_d () const noexcept

Qudit dimension.

std::vector< cmat > get\_Ks () const

Vector of noise operators.

std::vector< double > get\_probs () const

Vector of probabilities corresponding to each noise operator.

• idx get last idx () const

Index of the last occurring noise element.

double get\_last\_p () const

Probability of the last occurring noise element.

cmat get\_last\_K () const

Last occurring noise element.

· virtual cmat operator() (const cmat &state, idx target) const

Function invocation operator, applies the underlying noise model on qudit target of the multi-partite state vector or density matrix state.

virtual cmat operator() (const cmat &state, const std::vector < idx > &target) const

Function invocation operator, applies the underlying correlated noise model on qudits specified by target of the multipartite state vector or density matrix state.

#### **Protected Member Functions**

void compute\_probs\_ (const cmat &state, const std::vector < idx > &target) const
 Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

• cmat compute state (const cmat &state, const std::vector < idx > &target) const

Compute the resulting state after the noise was applied.

## **Protected Attributes**

const std::vector< cmat > Ks

Kraus operators.

std::vector< double > probs\_

probabilities

• idx d\_ {}

qudit dimension

idx i\_{}

index of the last occurring noise element

bool generated\_ {false}

invoked, or if the noise is state-independent

# 7.41.1 Detailed Description

```
\label{eq:template} \begin{split} \text{template} &< \text{class T}> \\ \text{class qpp::NoiseBase} &< \text{T}> \end{split}
```

Base class for all noise models, derive your particular noise model.

# 7.41.2 Member Typedef Documentation

# 7.41.2.1 noise\_type

```
template<class T>
using qpp::NoiseBase< T >::noise_type = T
```

## 7.41.3 Constructor & Destructor Documentation

## 7.41.3.1 NoiseBase() [1/2]

Constructs a noise instance for StateDependent noise type.

Note

SFINAEd-out for StateIndependent noise

### **Parameters**

Α	Eigen expression (state vector or density matrix)
Ks	Vector of noise (Kraus) operators that specify the noise
d	Subsystem dimension

### 7.41.3.2 NoiseBase() [2/2]

template<class T>

Constructs a noise instance for StateIndependent noise type.

Note

SFINAEd-out for StateDependent noise

#### **Parameters**

Α	Eigen expression (state vector or density matrix)
Ks	Vector of noise (Kraus) operators that specify the noise
d	Subsystem dimension

# 7.41.3.3 ∼NoiseBase()

```
template<class T>
virtual qpp::NoiseBase< T >::~NoiseBase ( ) [virtual], [default]
```

Default virtual destructor.

## 7.41.4 Member Function Documentation

## 7.41.4.1 compute\_probs\_()

Compute probability outcomes for StateDependent noise type, otherwise returns without performing any operation (no-op)

#### **Parameters**

state	State vector or density matrix
target	Qudit indexes where the noise is applied

## 7.41.4.2 compute\_state\_()

Compute the resulting state after the noise was applied.

#### **Parameters**

state	State vector or density matrix
target	Qudit indexes where the noise is applied

### Returns

Resulting state after the noise was applied

## 7.41.4.3 get\_d()

```
template<class T>
idx qpp::NoiseBase< T >::get_d ( ) const [inline], [noexcept]
```

Qudit dimension.

## Returns

Qudit dimension

# 7.41.4.4 get\_Ks()

```
template<class T>
std::vector<cmat> qpp::NoiseBase< T >::get_Ks () const [inline]
```

Vector of noise operators.

## Returns

Vector of noise operators

```
7.41.4.5 get_last_idx()
```

```
template<class T>
idx qpp::NoiseBase< T >::get_last_idx ( ) const [inline]
```

Index of the last occurring noise element.

Returns

Index of the last occurring noise element

```
7.41.4.6 get_last_K()
```

```
template<class T>
cmat qpp::NoiseBase< T >::get_last_K ( ) const [inline]
```

Last occurring noise element.

Returns

Last occurring noise element

```
7.41.4.7 get_last_p()
```

```
template<class T>
double qpp::NoiseBase< T >::get_last_p ( ) const [inline]
```

Probability of the last occurring noise element.

Returns

Probability of the last occurring noise element

```
7.41.4.8 get_probs()
```

```
template<class T>
std::vector<double> qpp::NoiseBase< T >::get_probs ( ) const [inline]
```

Vector of probabilities corresponding to each noise operator.

Returns

Probability vector

```
7.41.4.9 operator()() [1/2]
```

Function invocation operator, applies the underlying noise model on qudit *target* of the multi-partite state vector or density matrix *state*.

#### **Parameters**

state	Multi-partite state vector or density matrix
target	Qudit index where the noise is applied

#### Returns

Resulting state vector or density matrix

## **7.41.4.10** operator()() [2/2]

Function invocation operator, applies the underlying correlated noise model on qudits specified by *target* of the multi-partite state vector or density matrix *state*.

#### **Parameters**

state	Multi-partite state vector or density matrix
target	Qudit indexes where the correlated noise is applied

## Returns

Resulting state vector or density matrix

#### 7.41.5 Member Data Documentation

### 7.41.5.1 d\_

```
template<class T>
idx qpp::NoiseBase< T >::d_ {} [mutable], [protected]
qudit dimension
```

# 7.41.5.2 generated\_

```
template<class T>
bool qpp::NoiseBase< T >::generated_ {false} [mutable], [protected]
```

invoked, or if the noise is state-independent

set to true after compute\_state\_() is

#### 7.41.5.3 i\_

```
template<class T>
idx qpp::NoiseBase< T >::i_ {} [mutable], [protected]
```

index of the last occurring noise element

#### 7.41.5.4 Ks\_

```
template<class T>
const std::vector<cmat> qpp::NoiseBase< T >::Ks_ [protected]
```

Kraus operators.

#### 7.41.5.5 probs

```
template<class T>
std::vector<double> qpp::NoiseBase< T >::probs_ [mutable], [protected]
```

#### probabilities

The documentation for this class was generated from the following file:

• classes/noise.h

# 7.42 qpp::NoiseType Class Reference

Contains template tags used to specify the noise type.

```
#include <classes/noise.h>
```

## Classes

class StateDependent

Template tag, used whenever the noise is state-dependent.

· class StateIndependent

Template tag, used whenever the noise is state-independent.

# 7.42.1 Detailed Description

Contains template tags used to specify the noise type.

The documentation for this class was generated from the following file:


· classes/noise.h

# 7.43 qpp::exception::NotBipartite Class Reference


Not bi-partite exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotBipartite:



Collaboration diagram for qpp::exception::NotBipartite:



## **Public Member Functions**

• std::string type\_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

# 7.43.1 Detailed Description

Not bi-partite exception.

std::vector<idx> of dimensions has size different from 2

## 7.43.2 Member Function Documentation

## 7.43.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred
-------	--

# 7.43.2.2 type\_description()

```
std::string qpp::exception::NotBipartite::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

### Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.44 qpp::exception::NotImplemented Class Reference


Code not yet implemented.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotImplemented:



Collaboration diagram for qpp::exception::NotImplemented:



## **Public Member Functions**

• std::string type\_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

# 7.44.1 Detailed Description

Code not yet implemented.

#### 7.44.2 Member Function Documentation

## 7.44.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where Text representing where the exception occurred

## 7.44.2.2 type\_description()

```
std::string qpp::exception::NotImplemented::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

### Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.45 qpp::exception::NotQubitCvector Class Reference


Column vector is not 2 x 1 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitCvector:



Collaboration diagram for qpp::exception::NotQubitCvector:



## **Public Member Functions**

• std::string type\_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

# 7.45.1 Detailed Description

Column vector is not 2 x 1 exception.

Eigen::Matrix is not 2 x 1

## 7.45.2 Member Function Documentation

## 7.45.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

where Text representing where the exception occurred

# 7.45.2.2 type\_description()

std::string qpp::exception::NotQubitCvector::type\_description ( ) const [inline], [override],
[virtual]

Exception type description.

### Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.46 qpp::exception::NotQubitMatrix Class Reference


Matrix is not 2 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitMatrix:



Collaboration diagram for qpp::exception::NotQubitMatrix:



# **Public Member Functions**

• std::string type\_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

# 7.46.1 Detailed Description

Matrix is not 2 x 2 exception.

Eigen::Matrix is not 2 x 2

# 7.46.2 Member Function Documentation

# 7.46.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

where Text representing where the exception occurred

# 7.46.2.2 type\_description()

std::string qpp::exception::NotQubitMatrix::type\_description ( ) const [inline], [override],
[virtual]

Exception type description.

### Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.47 qpp::exception::NotQubitRvector Class Reference


Row vector is not 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitRvector:



Collaboration diagram for qpp::exception::NotQubitRvector:



# **Public Member Functions**

• std::string type\_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

# 7.47.1 Detailed Description

Row vector is not 1 x 2 exception.

Eigen::Matrix is not 1 x 2

# 7.47.2 Member Function Documentation

# 7.47.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

where Text representing where the exception occurred

# 7.47.2.2 type\_description()

std::string qpp::exception::NotQubitRvector::type\_description ( ) const [inline], [override],
[virtual]

Exception type description.

### Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.48 qpp::exception::NotQubitSubsys Class Reference


Subsystems are not qubits exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitSubsys:



Collaboration diagram for qpp::exception::NotQubitSubsys:



# **Public Member Functions**

• std::string type\_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

# 7.48.1 Detailed Description

Subsystems are not qubits exception.

Subsystems are not 2-dimensional (qubits)

# 7.48.2 Member Function Documentation

# 7.48.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred
-------	--

# 7.48.2.2 type\_description()

```
std::string qpp::exception::NotQubitSubsys::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

### Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.49 qpp::exception::NotQubitVector Class Reference


Vector is not 2 x 1 nor 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitVector:



Collaboration diagram for qpp::exception::NotQubitVector:



# **Public Member Functions**

• std::string type\_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

# 7.49.1 Detailed Description

Vector is not 2 x 1 nor 1 x 2 exception.

Eigen::Matrix is not 2 x 1 nor 1 x 2

# 7.49.2 Member Function Documentation

# 7.49.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

where Text representing where the exception occurred

# 7.49.2.2 type\_description()

std::string qpp::exception::NotQubitVector::type\_description ( ) const [inline], [override],
[virtual]

Exception type description.

### Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.50 qpp::exception::OutOfRange Class Reference


Argument out of range exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::OutOfRange:



Collaboration diagram for qpp::exception::OutOfRange:



# **Public Member Functions**

• std::string type\_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

# 7.50.1 Detailed Description

Argument out of range exception.

Argument out of range

# 7.50.2 Member Function Documentation

# 7.50.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred
-------	--

# 7.50.2.2 type\_description()

```
std::string qpp::exception::OutOfRange::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

### Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.51 qpp::exception::PermInvalid Class Reference


Invalid permutation exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermInvalid:



Collaboration diagram for qpp::exception::PermInvalid:



# **Public Member Functions**

• std::string type\_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

# 7.51.1 Detailed Description

Invalid permutation exception.

std::vector<idx> does note represent a valid permutation

# 7.51.2 Member Function Documentation

# 7.51.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred
-------	--

# 7.51.2.2 type\_description()

```
std::string qpp::exception::PermInvalid::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

### Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.52 qpp::exception::PermMismatchDims Class Reference


Permutation mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermMismatchDims:



Collaboration diagram for qpp::exception::PermMismatchDims:



# **Public Member Functions**

• std::string type\_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

# 7.52.1 Detailed Description

Permutation mismatch dimensions exception.

Size of the std::vector<idx> representing the permutation is different from the size of the std::vector<idx> of dimensions

## 7.52.2 Member Function Documentation

## 7.52.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

### **Parameters**

# 7.52.2.2 type\_description()

```
std::string qpp::exception::PermMismatchDims::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

# Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.53 qpp::QCircuit Class Reference


Quantum circuit class.

#include <classes/circuits.h>

Inheritance diagram for qpp::QCircuit:



Collaboration diagram for qpp::QCircuit:



# Classes

struct GateStep

One step consisting only of gates/operators in the circuit.

· class iterator

Quantum circuit bound-checking (safe) iterator.

struct MeasureStep

One step consisting only of measurements in the circuit.

# **Public Types**

enum GateType {
 GateType::NONE, GateType::SINGLE, GateType::TWO, GateType::THREE,
 GateType::CUSTOM, GateType::FAN, GateType::QFT, GateType::TFQ,
 GateType::SINGLE\_CTRL\_SINGLE\_TARGET, GateType::SINGLE\_CTRL\_MULTIPLE\_TARGET, GateType::MULTIPLE\_CTR

GateType::MULTIPLE\_CTRL\_MULTIPLE\_TARGET,

GateType::CUSTOM\_CTRL, GateType::SINGLE\_cCTRL\_SINGLE\_TARGET, GateType::SINGLE\_cCTRL\_MULTIPLE\_TARGE GateType::MULTIPLE cCTRL SINGLE TARGET,

GateType::MULTIPLE\_cCTRL\_MULTIPLE\_TARGET, GateType::CUSTOM\_cCTRL }

Type of gate being executed in a gate step.

 enum MeasureType { MeasureType::NONE, MeasureType::MEASURE\_Z, MeasureType::MEASURE\_V, MeasureType::MEASURE\_V\_MANY }

Type of measurement being executed in a measurement step.

enum StepType { StepType::NONE, StepType::GATE, StepType::MEASUREMENT }

Types of each step in the quantum circuit.

· using const iterator = iterator

both iterators are const\_iterators

#### **Public Member Functions**

· iterator begin ()

Iterator to the first element.

· const iterator begin () const noexcept

Constant iterator to the first element.

· const iterator cbegin () const noexcept

Constant iterator to the first element.

• iterator end ()

Iterator to the next to the last element.

const\_iterator end () const noexcept

Constant iterator to the next to the last element.

· const iterator cend () const noexcept

Constant iterator to the next to the last element.

QCircuit (idx nq, idx nc=0, idx d=2, std::string name="")

Constructs a quantum circuit.

virtual ~QCircuit ()=default

Default virtual destructor.

• idx get\_nq () const noexcept

Total number of qudits in the circuit.

• idx get\_nc () const noexcept

Total number of classical dits in the circuit.

• idx get\_d () const noexcept

Dimension of the comprising qudits.

• std::string get\_name () const

Quantum circuit name.

· idx get measured (idx i) const

Check whether qudit i was already measured.

std::vector< idx > get measured () const

Vector of already measured qudit indexes.

std::vector< idx > get\_non\_measured () const

Vector of non-measured qudit indexes.

· idx get\_gate\_count () const noexcept

Quantum circuit total gate count.

· idx get gate count (const std::string &name) const

Quantum circuit gate count.

idx get\_gate\_depth () const

Quantum circuit total gate depth.

• idx get\_gate\_depth (const std::string &name QPP\_UNUSED\_) const

Quantum circuit gate depth.

idx get\_measurement\_count () const noexcept

Quantum circuit total measurement count.

• idx get measurement count (const std::string &name) const

Quantum circuit measurement count.

• idx get\_step\_count () const noexcept

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

QCircuit & gate (const cmat &U, idx i, std::string name="")

Applies the single qudit gate U on single qudit i.

QCircuit & gate (const cmat &U, idx i, idx j, std::string name="")

Applies the two qudit gate U on qudits i and j.

QCircuit & gate (const cmat &U, idx i, idx j, idx k, std::string name="")

Applies the three qudit gate U on qudits i, j and k.

QCircuit & gate\_fan (const cmat &U, const std::vector< idx > &target, std::string name="")

Applies the single qudit gate U on every qudit listed in target.

• QCircuit & gate\_fan (const cmat &U, const std::initializer\_list< idx > &target, std::string name=""")

Applies the single qudit gate U on every qudit listed in target.

QCircuit & gate fan (const cmat &U, std::string name="")

Applies the single qudit gate U on every remaining non-measured qudit.

• QCircuit & gate\_custom (const cmat &U, const std::vector < idx > &target, std::string name="")

Jointly applies the custom multiple qudit gate U on the qudit indexes specified by target.

QCircuit & QFT (const std::vector < idx > &target, bool swap QPP\_UNUSED\_=true)

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & TFQ (const std::vector < idx > &target, bool swap QPP\_UNUSED\_=true)

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuit & CTRL (const cmat &U, idx ctrl, idx target, std::string name="")

Applies the single qudit controlled gate U with control qudit ctrl and target qudit target.

QCircuit & CTRL (const cmat &U, idx ctrl, const std::vector < idx > &target, std::string name="")

Applies the single qudit controlled gate U with control qudit ctrl on every qudit listed in target.

QCircuit & CTRL (const cmat &U, const std::vector< idx > &ctrl, idx target, std::string name="")

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on the target qudit target.

QCircuit & CTRL (const cmat &U, const std::vector < idx > &ctrl, const std::vector < idx > &target, std::string name="")

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on every qudit listed in target.

QCircuit & CTRL\_custom (const cmat &U, const std::vector < idx > &ctrl, const std::vector < idx > &target, std::string name="")

Jointly applies the custom multiple-qudit controlled gate U with multiple control qudits listed in ctrl on the qudit indexes specified by target.

• QCircuit & cCTRL (const cmat &U, idx ctrl dit, idx target, std::string name="")

Applies the single qubit controlled gate U with classical control dit ctrl and target qudit target.

QCircuit & cCTRL (const cmat &U, idx ctrl\_dit, const std::vector < idx > &target, std::string name="")

Applies the single qudit controlled gate U with classical control dit ctrl on every qudit listed in target.

QCircuit & cCTRL (const cmat &U, const std::vector < idx > &ctrl dits, idx target, std::string name="")

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on the target qudit target.

QCircuit & cCTRL (const cmat &U, const std::vector< idx > &ctrl\_dits, const std::vector< idx > &target, std::string name="")

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on every qudit listed in target.

QCircuit & cCTRL\_custom (const cmat &U, const std::vector< idx > &ctrl\_dits, const std::vector< idx > &target, std::string name="")

Jointly applies the custom multiple-qudit controlled gate U with multiple classical control dits listed in ctrl on the qudit indexes specified by target.

QCircuit & measureZ (idx target, idx c\_reg, std::string name="")

Measurement of single qudit in the computational basis (Z-basis)

QCircuit & measureV (const cmat &V, idx target, idx c\_reg, std::string name="")

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

QCircuit & measureV (const cmat &V, const std::vector< idx > &target, idx c\_reg, std::string name="")

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix  $\nu$ 

 std::string to\_JSON (bool enclosed\_in\_curly\_brackets=true) const override *qpp::IJOSN::to\_JSON() override*

#### **Private Member Functions**

const std::vector< MeasureStep > & get\_measurements\_ () const noexcept

Vector of qpp::QCircuit::MeasureStep.

const std::vector < GateStep > & get\_gates\_ () const noexcept

Vector of qpp::QCircuit::GateStep.

std::ostream & display (std::ostream &os) const override

qpp::IDisplay::display() override

### **Private Attributes**

```
    const idx nq_
```

number of audits

const idx nc

number of classical "dits"

const idx d

qudit dimension

• std::string name\_

optional circuit name

• std::vector< bool > measured\_

keeps track of the measured qudits

std::unordered\_map< std::string, idx > depth\_

keeps track of the gate depths

• std::unordered map< std::string, idx > count

keeps track of the gate counts

std::unordered\_map< std::string, idx > measurement\_count\_

keeps track of the measurement counts

• std::vector< GateStep > gates\_{}

gates

std::vector< MeasureStep > measurements\_{}{}

measurements

std::vector< StepType > step\_types\_{}

type of each step

### **Friends**

- class QEngine
- std::ostream & operator<< (std::ostream &os, const GateType &gate\_type)

Extraction operator overload for qpp::QCircuit::GateType enum class.

• std::ostream & operator<< (std::ostream &os, const GateStep &gate\_step)

Extraction operator overload for qpp::QCircuit::GateStep class.

• std::ostream & operator<< (std::ostream &os, const MeasureType &measure\_type)

Extraction operator overload for qpp::QCircuit::MeasureType enum class.

std::ostream & operator<< (std::ostream &os, const MeasureStep &measure\_step)</li>

Extraction operator overload for qpp::QCircuit::MeasureStep class.

# 7.53.1 Detailed Description

Quantum circuit class.

See also

qpp::QEngine

# 7.53.2 Member Typedef Documentation

### 7.53.2.1 const\_iterator

```
using qpp::QCircuit::const_iterator = iterator
```

both iterators are const\_iterators

## 7.53.3 Member Enumeration Documentation

# 7.53.3.1 GateType

```
enum qpp::QCircuit::GateType [strong]
```

Type of gate being executed in a gate step.

#### **Enumerator**

NONE	represents no gate
SINGLE	unitary gate on a single qudit
TWO	unitary gate on 2 qudits
THREE	unitary gate on 3 qudits
CUSTOM	custom gate on multiple qudits

# Enumerator

FAN	same unitary gate on multiple qudits
QFT	quantum Fourier transform,
TFQ	quantum inverse Fourier transform,
SINGLE_CTRL_SINGLE_TARGET	one control and one target controlled 1 qudit unitary gate with
SINGLE_CTRL_MULTIPLE_TARGET	one control and multiple targets controlled 1 qudit unitary gate with
MULTIPLE_CTRL_SINGLE_TARGET	multiple controls and single target controlled 1 qudit unitary gate with
MULTIPLE_CTRL_MULTIPLE_TARGET	multiple controls and multiple targets controlled 1 qudit unitary gate with
CUSTOM_CTRL	and multiple targets custom controlled gate with multiple controls
SINGLE_cCTRL_SINGLE_TARGET	one classical control and one target controlled 1 qudit unitary gate with
SINGLE_cCTRL_MULTIPLE_TARGET	one classical control and multiple targets controlled 1 qudit unitary gate with
MULTIPLE_cCTRL_SINGLE_TARGET	multiple classical controls and single target controlled 1 qudit unitary gate with
MULTIPLE_cCTRL_MULTIPLE_TARGET	with multiple classical controls and multiple targets controlled 1 qudit unitary gate
CUSTOM_cCTRL	multiple targets custom controlled gate with multiple controls and

# 7.53.3.2 MeasureType

```
enum qpp::QCircuit::MeasureType [strong]
```

Type of measurement being executed in a measurement step.

# Enumerator

NONE	represents no measurement
MEASURE_Z	Z measurement of single qudit.
MEASURE_V	or rank-1 projectors specified by the columns of matrix $V$ measurement of single qudit in the orthonormal basis
MEASURE_V_MANY	basis or rank-1 projectors specified by the columns of matrix $\it{V}$ measurement of multiple qudits in the orthonormal

# 7.53.3.3 StepType

```
enum qpp::QCircuit::StepType [strong]
```

Types of each step in the quantum circuit.

# Enumerator

NONE	represents no step
GATE	quantum gate
MEASUREMENT	measurement

# 7.53.4 Constructor & Destructor Documentation

# 7.53.4.1 QCircuit()

```
qpp::QCircuit::QCircuit (
    idx nq,
    idx nc = 0,
    idx d = 2,
    std::string name = "" ) [inline], [explicit]
```

Constructs a quantum circuit.

# Note

The measurement results can only be stored in the classical dits of which number is specified by nc

# **Parameters**

nq	Number of qbits	
nc	Number of classical dits	
d	Subsystem dimensions (optional, default is qubit, i.e. $d = 2$ )	
name	Circuit name (optional)	

# 7.53.4.2 ~QCircuit()

```
virtual qpp::QCircuit::~QCircuit ( ) [virtual], [default]
```

Default virtual destructor.

# 7.53.5 Member Function Documentation

```
7.53.5.1 begin() [1/2]
```

```
iterator qpp::QCircuit::begin ( ) [inline]
```

Iterator to the first element.

Returns

Iterator to the first element

```
7.53.5.2 begin() [2/2]
const_iterator qpp::QCircuit::begin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

# Returns

Constant iterator to the first element

### 7.53.5.3 cbegin()

```
const_iterator qpp::QCircuit::cbegin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

## Returns

Constant iterator to the first element

idx target,

std::string name = "" ) [inline]

Applies the single qubit controlled gate U with classical control dit ctrl and target qudit target.

## **Parameters**

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit index
name	Optional gate name

Generated by Doxygen

#### Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with classical control dit *ctrl* on every qudit listed in *target*.

#### **Parameters**

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit indexes; the gate $U$ is applied on every one of them depending on the values of the
	classical control dits
name	Optional gate name

### Returns

Reference to the current instance

```
7.53.5.6 cCTRL() [3/4]
```

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the target qudit *target*.

# **Parameters**

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit index
name	Optional gate name

# Returns

Reference to the current instance

### 7.53.5.7 cCTRL() [4/4]

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on every qudit listed in *target*.

### **Parameters**

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit indexes; the gate $U$ is applied on every one of them depending on the values of the
	classical control dits
name	Optional gate name

#### Returns

Reference to the current instance

# 7.53.5.8 cCTRL\_custom()

Jointly applies the custom multiple-qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the qudit indexes specified by *target*.

# **Parameters**

U	Multiple-qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit indexes where the gate $U$ is applied depending on the values of the classical control dits
name	Optional gate name

#### Returns

Reference to the current instance

7.53.5.9 cend()

```
const_iterator qpp::QCircuit::cend ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

# Returns

Constant iterator to the next to the last element

Applies the single qudit controlled gate *U* with control qudit *ctrl* and target qudit *target*.

#### **Parameters**

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit index
name	Optional gate name

## Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with control qudit *ctrl* on every qudit listed in *target*.

### **Parameters**

U	Single qudit quantum gate	
ctrl	Control qudit index	
target	Target qudit indexes; the gate <i>U</i> is applied on every one of them depending on the values of the control qudits	
Gen <i>enahe</i> d b	ν <b>Οργίτο</b> παl gate name	

### Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the target qudit *target*.

#### **Parameters**

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit index
name	Optional gate name

# Returns

Reference to the current instance

```
7.53.5.13 CTRL() [4/4]
```

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on every qudit listed in *target*.

### **Parameters**

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes; the gate $U$ is applied on every one of them depending on the values of the control qudits
name	Optional gate name

#### Returns

Reference to the current instance

# 7.53.5.14 CTRL\_custom()

Jointly applies the custom multiple-qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the qudit indexes specified by *target*.

#### **Parameters**

U	Multiple-qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes where the gate $U$ is applied depending on the values of the control qudits
name	Optional gate name

# Returns

Reference to the current instance

# 7.53.5.15 display()

# qpp::IDisplay::display() override

Writes to the output stream a textual representation of the quantum circuit

### **Parameters**

```
os Output stream passed by reference
```

# Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.53.5.16 end() [1/2]
```

```
iterator qpp::QCircuit::end ( ) [inline]
```

Iterator to the next to the last element.

# Returns

Iterator to the next to the last element

```
7.53.5.17 end() [2/2]
const_iterator qpp::QCircuit::end ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

# Returns

Constant iterator to the next to the last element

Applies the single qudit gate *U* on single qudit *i*.

### **Parameters**

U	Single qudit quantum gate
i	Qudit index
name	Optional gate name

### Returns

Reference to the current instance

```
idx i,
idx j,
std::string name = "" ) [inline]
```

Applies the two qudit gate U on qudits i and j.

### **Parameters**

U	Two qudit quantum gate
i	Qudit index
j	Qudit index
name	Optional gate name

### Returns

Reference to the current instance

```
7.53.5.20 gate() [3/3]
```

Applies the three qudit gate U on qudits i, j and k.

# **Parameters**

U	Three qudit quantum gate
i	Qudit index
j	Qudit index
k	Qudit index
name	Optional gate name

# Returns

Reference to the current instance

# 7.53.5.21 gate\_custom()

Jointly applies the custom multiple qudit gate *U* on the qudit indexes specified by *target*.

# **Parameters**

U	Multiple qudit quantum gate
target	Subsystem indexes where the gate $U$ is applied
name	Optional gate name

### Returns

Reference to the current instance

Applies the single qudit gate *U* on every qudit listed in *target*.

# **Parameters**

U	Single qudit quantum gate
target	Target qudit indexes; the gate $U$ is applied on every one of them
name	Optional gate name

# Returns

Reference to the current instance

Applies the single qudit gate U on every qudit listed in target.

# **Parameters**

U	Single qudit quantum gate
target	Target qudit indexes; the gate $U$ is applied on every one of them
name	Optional gate name

#### Returns

Reference to the current instance

Applies the single qudit gate U on every remaining non-measured qudit.

### **Parameters**

U	Single qudit quantum gate
name	Optional gate name

### Returns

Reference to the current instance

```
7.53.5.25 get_d()
idx qpp::QCircuit::get_d ( ) const [inline], [noexcept]
```

Dimension of the comprising qudits.

### Returns

Qudit dimension

```
7.53.5.26 get_gate_count() [1/2]
idx qpp::QCircuit::get_gate_count ( ) const [inline], [noexcept]
```

Quantum circuit total gate count.

#### Returns

Total gate count

Quantum circuit gate count.

Da			_ 1		
Pа	ra	m	eı	re	rs

```
name Gate name
```

Returns

Gate count

```
7.53.5.28 get_gate_depth() [1/2]
idx qpp::QCircuit::get_gate_depth ( ) const [inline]
```

Quantum circuit total gate depth.

Returns

Total gate depth

```
7.53.5.29 get_gate_depth() [2/2]
```

Quantum circuit gate depth.

**Parameters** 

```
name Gate name
```

Returns

Gate depth

```
7.53.5.30 get_gates_()
```

```
\verb|const| std::vector < \verb|GateStep>& qpp::QCircuit::get_gates_ ( ) const [inline], [private], [noexcept]| \\
```

Vector of qpp::QCircuit::GateStep.

Returns

Vector of qpp::QCircuit::GateStep

```
7.53.5.31 get_measured() [1/2]
```

Check whether qudit *i* was already measured.

# **Parameters**

```
i Qudit index
```

#### Returns

True if qudit i was already measured, false othwewise

```
7.53.5.32 get_measured() [2/2]
std::vector<idx> qpp::QCircuit::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

#### Returns

Vector of already measured qudit indexes

```
7.53.5.33 get_measurement_count() [1/2]
```

```
idx qpp::QCircuit::get_measurement_count ( ) const [inline], [noexcept]
```

Quantum circuit total measurement count.

# Returns

Total measurement count

# **7.53.5.34** get\_measurement\_count() [2/2]

Quantum circuit measurement count.

### **Parameters**

name Measurement name

# Returns

Measurement count

# 7.53.5.35 get\_measurements\_()

```
const std::vector<MeasureStep>& qpp::QCircuit::get_measurements_ ( ) const [inline], [private],
[noexcept]
```

Vector of qpp::QCircuit::MeasureStep.

### Returns

Vector of qpp::QCircuit::MeasureStep

# 7.53.5.36 get\_name()

```
std::string qpp::QCircuit::get_name ( ) const [inline]
```

Quantum circuit name.

### Returns

Quantum circuit name

### 7.53.5.37 get\_nc()

```
idx qpp::QCircuit::get_nc ( ) const [inline], [noexcept]
```

Total number of classical dits in the circuit.

### Returns

Total number of classical dits

```
7.53.5.38 get_non_measured()
```

```
std::vector<idx> qpp::QCircuit::get_non_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

### Returns

Vector of non-measured qudit indexes

```
7.53.5.39 get_nq()
```

```
idx qpp::QCircuit::get_nq ( ) const [inline], [noexcept]
```

Total number of qudits in the circuit.

#### Returns

Total number of qudits

```
7.53.5.40 get_step_count()
```

```
idx qpp::QCircuit::get_step_count ( ) const [inline], [noexcept]
```

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

# Returns

Total (gates + measurements) count

# **7.53.5.41** measureV() [1/2]

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

### **Parameters**

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V	
target	Qudit index	
Generated b	y Classical register where the value of the measurement is stored	
name	Optional measurement name	

### Returns

Reference to the current instance

# **7.53.5.42** measureV() [2/2]

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

### **Parameters**

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V
target	Target qudit indexes that are jointly measured
c_reg	Classical register where the value of the measurement is stored
name	Optional measurement name

# Returns

Reference to the current instance

# 7.53.5.43 measureZ()

```
QCircuit& qpp::QCircuit::measureZ (
         idx target,
         idx c_reg,
         std::string name = "" ) [inline]
```

Measurement of single qudit in the computational basis (Z-basis)

# **Parameters**

target	Qudit index
c_reg	Classical register where the value of the measurement is being stored
name	Optional measurement name, default is "Measure Z"

#### Returns

Reference to the current instance

### 7.53.5.44 QFT()

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

## **Parameters**

target	Subsystem indexes where the quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

### Returns

Reference to the current instance

## 7.53.5.45 TFQ()

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

### **Parameters**

target	Subsystem indexes where the inverse quantum Fourier transform is applied	
swap	Swaps the qubits at the end (true by default)	

#### Returns

Reference to the current instance

### 7.53.5.46 to\_JSON()

qpp::IJOSN::to\_JSON() override

Displays the quantum circuit in JSON format

### **Parameters**

enclosed_in_curly_brackets	If true, encloses the result in curly brackets
----------------------------	--

## Returns

String containing the JSON representation of the quantum circuit

Implements qpp::IJSON.

# 7.53.6 Friends And Related Function Documentation

Extraction operator overload for qpp::QCircuit::GateType enum class.

### **Parameters**

os	Output stream
gate_type	qpp::QCircuit::GateType enum class

## Returns

Output stream

```
7.53.6.2 operator << [2/4]
```

Extraction operator overload for qpp::QCircuit::GateStep class.

### **Parameters**

os	Output stream
gate type	qpp::QCircuit::GateStep class

### Returns

Output stream

Extraction operator overload for qpp::QCircuit::MeasureType enum class.

### **Parameters**

os	Output stream
gate_type	qpp::QCircuit::MeasureType enum class

### Returns

Output stream

Extraction operator overload for qpp::QCircuit::MeasureStep class.

### **Parameters**

os	Output stream
gate_type	qpp::QCircuit::MeasureStep enum class

# Returns

Output stream

## 7.53.6.5 QEngine

```
friend class QEngine [friend]
```

# 7.53.7 Member Data Documentation

keeps track of the measured qudits

```
7.53.7.1 count_
std::unordered_map<std::string, idx> qpp::QCircuit::count_ [private]
keeps track of the gate counts
7.53.7.2 d_
const idx qpp::QCircuit::d_ [private]
qudit dimension
7.53.7.3 depth_
std::unordered_map<std::string, idx> qpp::QCircuit::depth_ [private]
keeps track of the gate depths
7.53.7.4 gates_
std::vector<GateStep> qpp::QCircuit::gates_ {} [private]
gates
7.53.7.5 measured_
std::vector<bool> qpp::QCircuit::measured_ [private]
```

```
7.53.7.6 measurement_count_
std::unordered_map<std::string, idx> qpp::QCircuit::measurement_count_ [private]
keeps track of the measurement counts
7.53.7.7 measurements
std::vector<MeasureStep> qpp::QCircuit::measurements_ {} [private]
measurements
7.53.7.8 name_
std::string qpp::QCircuit::name_ [private]
optional circuit name
7.53.7.9 nc_
const idx qpp::QCircuit::nc_ [private]
number of classical "dits"
7.53.7.10 nq_
const idx qpp::QCircuit::nq_ [private]
number of qudits
7.53.7.11 step_types_
std::vector<StepType> qpp::QCircuit::step_types_ {} [private]
type of each step
```

Generated by Doxygen

· classes/circuits.h


The documentation for this class was generated from the following file:

# 7.54 qpp::QEngine Class Reference


Quantum circuit engine, executes qpp::QCircuit.

#include <classes/circuits.h>

Inheritance diagram for qpp::QEngine:



Collaboration diagram for qpp::QEngine:



# **Public Member Functions**

• QEngine (const QCircuit &qcd)

Constructs a quantum engine out of a quantum circuit.

• QEngine (QCircuit &&)=delete

Disables rvalue QCircuit.

virtual ~QEngine ()=default

Default virtual destructor.

• ket get\_psi () const

Underlying quantum state.

ket & get\_ref\_psi ()

Reference to the underlying quantum state.

• std::vector< idx > get\_dits () const

Vector with the values of the underlying classical dits.

• idx get\_dit (idx i) const

Value of the classical dit at position i.

std::vector< double > get\_probs () const

Vector of underlying measurement outcome probabilities.

bool get\_measured (idx i) const

Check whether qudit i was already measured.

• std::vector< idx > get\_measured () const

Vector of already measured qudit indexes.

std::vector< idx > get\_not\_measured () const

Vector of non-measured qudit indexes.

const QCircuit & get\_circuit () const noexcept

Quantum circuit.

• QEngine & set\_dit (idx i, idx value)

Sets the classical dit at position i.

· void reset ()

Resets the engine.

void execute (const QCircuit::iterator::value\_type &elem)

Executes one step in the quantum circuit.

void execute (const QCircuit::iterator &it)

Executes one step in the quantum circuit.

• std::string to\_JSON (bool enclosed\_in\_curly\_brackets=true) const override

qpp::IJOSN::to\_JSON() override

## **Protected Member Functions**

• void set\_measured\_ (idx i)

Marks qudit i as measured then re-label accordingly the remaining non-measured qudits.

std::vector< idx > get\_relative\_pos\_ (std::vector< idx > v)

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

### **Protected Attributes**

const QCircuit & qcd

quantum circuit

· ket psi\_

state vector

std::vector< idx > dits

classical dits

std::vector< double > probs

measurement probabilities

std::vector < idx > subsys\_

## **Private Member Functions**

• std::ostream & display (std::ostream &os) const override

qpp::IDisplay::display() override

# 7.54.1 Detailed Description

Quantum circuit engine, executes qpp::QCircuit.

See also

qpp::QCircuit

# 7.54.2 Constructor & Destructor Documentation

Constructs a quantum engine out of a quantum circuit.

Note

The quantum circuit must be an Ivalue

See also

```
qpp::QEngine(QCircuit&&)
```

Note

The initial underlying quantum state is set to  $|0\rangle^{\otimes n}$ 

### **Parameters**

```
qcd Quantum circuit
```

# **7.54.2.2 QEngine()** [2/2]

```
qpp::QEngine::QEngine (
          QCircuit && ) [delete]
```

Disables rvalue **QCircuit**.

```
7.54.2.3 ~QEngine()
```

```
\label{local_problem} \mbox{virtual qpp::QEngine::} \sim \mbox{QEngine ( ) [virtual], [default]}
```

Default virtual destructor.

# 7.54.3 Member Function Documentation

## 7.54.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the state of the engine

#### **Parameters**

```
os Output stream passed by reference
```

### Returns

Reference to the output stream

Implements qpp::IDisplay.

# **7.54.3.2 execute()** [1/2]

Executes one step in the quantum circuit.

#### **Parameters**

```
elem Step to be executed
```

```
7.54.3.3 execute() [2/2]
```

Executes one step in the quantum circuit.

#### **Parameters**

```
it Iterator to the step to be executed
```

```
7.54.3.4 get_circuit()
```

```
const QCircuit& qpp::QEngine::get_circuit ( ) const [inline], [noexcept]
```

Quantum circuit.

## Returns

Underlying quantum circuit

### 7.54.3.5 get\_dit()

```
idx qpp::QEngine::get_dit (
        idx i) const [inline]
```

Value of the classical dit at position i.

## **Parameters**

```
i Classical dit index
```

## Returns

Value of the classical dit at position i

```
7.54.3.6 get_dits()
```

```
std::vector<idx> qpp::QEngine::get_dits ( ) const [inline]
```

Vector with the values of the underlying classical dits.

# Returns

Vector of underlying classical dits

## **7.54.3.7** get\_measured() [1/2]

```
bool qpp::QEngine::get_measured ( \label{eq:decomposition} \mbox{idx $i$ ) const [inline]}
```

Check whether qudit i was already measured.

### **Parameters**

```
i Qudit index
```

#### Returns

True if qudit i was already measured, false othwewise

### 7.54.3.8 get\_measured() [2/2]

```
std::vector<idx> qpp::QEngine::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

#### Returns

Vector of already measured qudit indexes

## 7.54.3.9 get\_not\_measured()

```
std::vector<idx> qpp::QEngine::get_not_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

#### Returns

Vector of non-measured qudit indexes

### 7.54.3.10 get\_probs()

```
std::vector<double> qpp::QEngine::get_probs ( ) const [inline]
```

Vector of underlying measurement outcome probabilities.

### Note

The probability vector has the same length as the vector of classical dits. If the measurement result is stored at the index  $c\_reg$ , then the outcome probability is automatically stored at the same index  $c\_reg$  in the probability vector.

#### Returns

Vector of underlying measurement outcome probabilities

```
7.54.3.11 get_psi()
```

```
ket qpp::QEngine::get_psi ( ) const [inline]
```

Underlying quantum state.

Returns

Underlying quantum state

```
7.54.3.12 get_ref_psi()
```

```
ket& qpp::QEngine::get_ref_psi ( ) [inline]
```

Reference to the underlying quantum state.

Returns

Reference to the underlying quantum state

```
7.54.3.13 get_relative_pos_()
```

```
\label{eq:condition} $$ std::vector < idx > qpp::QEngine::get_relative_pos_ ( \\ std::vector < idx > v ) [inline], [protected] $$
```

Giving a vector *V* of non-measured qudits, get their relative position with respect to the measured qudits.

## **Parameters**



Returns

Vector of qudit indexes

```
7.54.3.14 reset()
```

```
void qpp::QEngine::reset ( ) [inline]
```

Resets the engine.

Re-initializes everything to zero and sets the initial state to  $|0\rangle^{\otimes n}$ 

### 7.54.3.15 set\_dit()

Sets the classical dit at position i.

## **Parameters**

i	Classical dit index
value	Classical dit value

### Returns

Reference to the current instance

# 7.54.3.16 set\_measured\_()

```
void qpp::QEngine::set_measured_ (
        idx i ) [inline], [protected]
```

Marks qudit *i* as measured then re-label accordingly the remaining non-measured qudits.

### **Parameters**

i Qudit index

# 7.54.3.17 to\_JSON()

qpp::IJOSN::to\_JSON() override

Displays the state of the engine in JSON format

#### **Parameters**

analogad in aurly brooksta	If true, encloses the result in curly brackets
enciosea in curiv brackeis	I il true, encloses the result in curiv brackets

### Returns

String containing the JSON representation of the state of the engine

Implements qpp::IJSON.

# 7.54.4 Member Data Documentation

```
7.54.4.1 dits
std::vector<idx> qpp::QEngine::dits_ [protected]
classical dits
7.54.4.2 probs_
std::vector<double> qpp::QEngine::probs_ [protected]
measurement probabilities
7.54.4.3 psi
ket qpp::QEngine::psi_ [protected]
state vector
7.54.4.4 qcd_
const QCircuit& qpp::QEngine::qcd_ [protected]
quantum circuit
7.54.4.5 subsys_
std::vector<idx> qpp::QEngine::subsys_ [protected]
```

• classes/circuits.h

keeps track of the measured subsystems, relabel them after measurements


The documentation for this class was generated from the following file:

# 7.55 qpp::QubitAmplitudeDampingNoise Class Reference


Qubit amplitude damping noise, as described in Nielsen and Chuang.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitAmplitudeDampingNoise:



Collaboration diagram for qpp::QubitAmplitudeDampingNoise:



# **Public Member Functions**

• QubitAmplitudeDampingNoise (double gamma)

Qubit amplitude damping noise constructor.

# **Additional Inherited Members**

# 7.55.1 Detailed Description

Qubit amplitude damping noise, as described in Nielsen and Chuang.

# 7.55.2 Constructor & Destructor Documentation

# 7.55.2.1 QubitAmplitudeDampingNoise()

Qubit amplitude damping noise constructor.

#### **Parameters**

ga	mma	Amplitude damping probability
----	-----	-------------------------------

The documentation for this class was generated from the following file:


· classes/noise.h

# 7.56 qpp::QubitBitFlipNoise Class Reference


Qubit bit flip noise.

```
#include <classes/noise.h>
```

 $Inheritance\ diagram\ for\ qpp::Qubit Bit Flip Noise:$ 



Collaboration diagram for qpp::QubitBitFlipNoise:



## **Public Member Functions**

• QubitBitFlipNoise (double p)

Qubit bit flip noise constructor.

## **Additional Inherited Members**

# 7.56.1 Detailed Description

Qubit bit flip noise.

# 7.56.2 Constructor & Destructor Documentation

# 7.56.2.1 QubitBitFlipNoise()

```
\label{eq:qpp::QubitBitFlipNoise} $$ \operatorname{qpp}::\operatorname{QubitBitFlipNoise} ($$ \operatorname{double} p ) [inline], [explicit] $$
```

Qubit bit flip noise constructor.

## **Parameters**

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

# 7.57 qpp::QubitBitPhaseFlipNoise Class Reference


Qubit bit-phase flip (dephasing) noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QubitBitPhaseFlipNoise:



Collaboration diagram for qpp::QubitBitPhaseFlipNoise:



# **Public Member Functions**

QubitBitPhaseFlipNoise (double p)
 Qubit bit-phase flip noise constructor.

# **Additional Inherited Members**

# 7.57.1 Detailed Description

Qubit bit-phase flip (dephasing) noise.

# 7.57.2 Constructor & Destructor Documentation

## 7.57.2.1 QubitBitPhaseFlipNoise()

```
\label{eq:qpp::QubitBitPhaseFlipNoise::QubitBitPhaseFlipNoise (} \\ \text{double } p \text{ ) } \quad \text{[inline], [explicit]}
```

Qubit bit-phase flip noise constructor.

### **Parameters**

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

# 7.58 qpp::QubitDepolarizingNoise Class Reference


Qubit depolarizing noise.

```
#include <classes/noise.h>
```

 $Inheritance\ diagram\ for\ qpp:: Qubit Depolarizing Noise:$ 



Collaboration diagram for qpp::QubitDepolarizingNoise:



## **Public Member Functions**

QubitDepolarizingNoise (double p)
 Qubit depolarizing noise constructor.

## **Additional Inherited Members**

# 7.58.1 Detailed Description

Qubit depolarizing noise.

## 7.58.2 Constructor & Destructor Documentation

# 7.58.2.1 QubitDepolarizingNoise()

```
\label{eq:qpp::QubitDepolarizingNoise::QubitDepolarizingNoise (} $$ double $p$ ) [inline], [explicit]
```

Qubit depolarizing noise constructor.

## **Parameters**

p Noise probability

The documentation for this class was generated from the following file:


· classes/noise.h

# 7.59 qpp::QubitPhaseDampingNoise Class Reference


Qubit phase damping noise, as described in Nielsen and Chuang.

```
#include <classes/noise.h>
```

Inheritance diagram for qpp::QubitPhaseDampingNoise:



Collaboration diagram for qpp::QubitPhaseDampingNoise:



# **Public Member Functions**

QubitPhaseDampingNoise (double lambda)
 Qubit phase damping noise constructor.

# **Additional Inherited Members**

# 7.59.1 Detailed Description

Qubit phase damping noise, as described in Nielsen and Chuang.

# 7.59.2 Constructor & Destructor Documentation

## 7.59.2.1 QubitPhaseDampingNoise()

Qubit phase damping noise constructor.

### **Parameters**

The documentation for this class was generated from the following file:


classes/noise.h

# 7.60 qpp::QubitPhaseFlipNoise Class Reference


Qubit phase flip (dephasing) noise.

```
#include <classes/noise.h>
```

 $Inheritance\ diagram\ for\ qpp::Qubit Phase Flip Noise:$ 



Collaboration diagram for qpp::QubitPhaseFlipNoise:



## **Public Member Functions**

• QubitPhaseFlipNoise (double p)

Qubit phase flip (dephasing) noise constructor.

## **Additional Inherited Members**

# 7.60.1 Detailed Description

Qubit phase flip (dephasing) noise.

# 7.60.2 Constructor & Destructor Documentation

# 7.60.2.1 QubitPhaseFlipNoise()

Qubit phase flip (dephasing) noise constructor.

## **Parameters**

p Noise probability

The documentation for this class was generated from the following file:


• classes/noise.h

# 7.61 qpp::exception::QuditAlreadyMeasured Class Reference


Qudit was already measured exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::QuditAlreadyMeasured:



Collaboration diagram for qpp::exception::QuditAlreadyMeasured:



## **Public Member Functions**

- std::string type\_description () const override
  - Exception type description.
- Exception (const std::string &where)

Constructs an exception.

# 7.61.1 Detailed Description

Qudit was already measured exception.

The qudit was already measured and cannot be measured again

# 7.61.2 Member Function Documentation

# 7.61.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

### **Parameters**

where	Text representing where the exception occurred
	Toxi representing where the exception eccurred

## 7.61.2.2 type\_description()

std::string qpp::exception::QuditAlreadyMeasured::type\_description ( ) const [inline], [override],
[virtual]

Exception type description.

## Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.62 qpp::QuditDepolarizingNoise Class Reference


Qudit depolarizing noise.

#include <classes/noise.h>

Inheritance diagram for qpp::QuditDepolarizingNoise:



Collaboration diagram for qpp::QuditDepolarizingNoise:



### **Public Member Functions**

QuditDepolarizingNoise (double p, idx d)
 Qudit depolarizing noise constructor.

# **Private Member Functions**

• std::vector< cmat > fill\_Ks\_ (idx d) const

Fills the Kraus operator vector.

std::vector< double > fill\_probs\_ (double p, idx d) const
 Fills the probability vector.

## **Additional Inherited Members**

# 7.62.1 Detailed Description

Qudit depolarizing noise.

### 7.62.2 Constructor & Destructor Documentation

## 7.62.2.1 QuditDepolarizingNoise()

```
qpp::QuditDepolarizingNoise::QuditDepolarizingNoise ( double p,  idx \ d \ ) \ \ [inline], \ [explicit]
```

Qudit depolarizing noise constructor.

### **Parameters**

р	Noise probability
d	Subsystem dimension

### 7.62.3 Member Function Documentation

Fills the Kraus operator vector.

### **Parameters**

d Qudit dimension

## Returns

Vector of Kraus operators representing the depolarizing noise

# 7.62.3.2 fill\_probs\_()

Fills the probability vector.

## **Parameters**

р	Probability
d	Qudit dimension

## Returns

Probability vector

The documentation for this class was generated from the following file:


• classes/noise.h

# 7.63 qpp::RandomDevices Class Reference


Singleton class that manages the source of randomness in the library.

#include <classes/random\_devices.h>

Inheritance diagram for qpp::RandomDevices:



Collaboration diagram for qpp::RandomDevices:



## **Public Member Functions**

• std::mt19937 & get\_prng ()

Returns a reference to the internal PRNG object.

std::istream & load (std::istream &is)

Loads the state of the PRNG from an input stream.

• std::ostream & save (std::ostream &os) const

Saves the state of the PRNG to an output stream.

### **Private Member Functions**

• RandomDevices ()

Initializes and seeds the random number generators.

∼RandomDevices ()=default

Default destructor.

## **Private Attributes**

 std::random\_device rd\_ used to seed std::mt19937 prng\_

std::mt19937 prng\_

Mersenne twister random number generator.

### **Friends**

class internal::Singleton < RandomDevices >

### **Additional Inherited Members**

## 7.63.1 Detailed Description

Singleton class that manages the source of randomness in the library.

# Warning

This class DOES NOT seed the standard C number generator used by Eigen::Matrix::Random(), since it is not thread safe. Do not use Eigen::Matrix::Random() or functions that depend on the C style random number engine, but use <a href="https://example.com/qpp::rand">qpp::rand()</a> instead!

#### 7.63.2 Constructor & Destructor Documentation

## 7.63.2.1 RandomDevices()

```
qpp::RandomDevices::RandomDevices ( ) [inline], [private]
```

Initializes and seeds the random number generators.

### 7.63.2.2 ∼RandomDevices()

```
\verb"qpp::RandomDevices::$\sim$RandomDevices ( ) [private], [default]
```

Default destructor.

# 7.63.3 Member Function Documentation

```
7.63.3.1 get_prng()
```

```
std::mt19937& qpp::RandomDevices::get_prng ( ) [inline]
```

Returns a reference to the internal PRNG object.

#### Returns

Reference to the internal PRNG object

## 7.63.3.2 load()

```
std::istream& qpp::RandomDevices::load (  \texttt{std::istream \& } is \ ) \quad [inline]
```

Loads the state of the PRNG from an input stream.

# **Parameters**

```
is Input stream
```

### Returns

The input stream

## 7.63.3.3 save()

Saves the state of the PRNG to an output stream.

#### **Parameters**

os Output stream

### Returns

The output stream

### 7.63.4 Friends And Related Function Documentation

```
7.63.4.1 internal::Singleton < Random Devices >
```

```
friend class internal::Singleton< RandomDevices > [friend]
```

## 7.63.5 Member Data Documentation

```
7.63.5.1 prng_
```

```
std::mt19937 qpp::RandomDevices::prng_ [private]
```

Mersenne twister random number generator.

```
7.63.5.2 rd_
```

```
std::random_device qpp::RandomDevices::rd_ [private]
```

used to seed std::mt19937 prng\_

The documentation for this class was generated from the following file:

• classes/random\_devices.h

# 7.64 qpp::internal::Singleton < T > Class Template Reference

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

```
#include <internal/classes/singleton.h>
```

### **Static Public Member Functions**

- static T & get\_instance () noexcept(std::is\_nothrow\_constructible < T >::value)
- static T & get\_thread\_local\_instance () noexcept(std::is\_nothrow\_constructible < T >::value)

### **Protected Member Functions**

- Singleton () noexcept=default
- Singleton (const Singleton &)=delete
- Singleton & operator= (const Singleton &)=delete
- virtual ∼Singleton ()=default

# 7.64.1 Detailed Description

```
template<typename T> class qpp::internal::Singleton< T>
```

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

To implement a singleton, derive your class from qpp::internal::Singleton, make qpp::internal::Singleton a friend of your class, then declare the constructor and destructor of your class as private. To get an instance, use the static member function qpp::internal::Singleton::get\_instance() (qpp::internal::Singleton::get\_thread\_local\_instance()), which returns a reference (thread\_local\_reference) to your newly created singleton (thread-safe in C++11).

### Example:

#### See also

Code of qpp::Codes, qpp::Gates, qpp::Init, qpp::RandomDevices, qpp::States or qpp.h for real world examples of usage.

#### 7.64.2 Constructor & Destructor Documentation

```
7.64.2.1 Singleton() [1/2]
template<typename T>
qpp::internal::Singleton < T >::Singleton ( ) [protected], [default], [noexcept]
7.64.2.2 Singleton() [2/2]
template<typename T>
qpp::internal::Singleton < T >::Singleton (
            const Singleton< T > \& ) [protected], [delete]
7.64.2.3 ∼Singleton()
template<typename T>
virtual qpp::internal::Singleton < T >::~Singleton ( ) [protected], [virtual], [default]
7.64.3 Member Function Documentation
7.64.3.1 get_instance()
template<typename T>
static T& qpp::internal::Singleton< T >::get_instance ( ) [inline], [static], [noexcept]
7.64.3.2 get_thread_local_instance()
template<typename T>
static T& qpp::internal::Singleton< T >::get_thread_local_instance ( ) [inline], [static],
[noexcept]
7.64.3.3 operator=()
template<typename T>
Singleton& qpp::internal::Singleton< T >::operator= (
             const Singleton< T > \& ) [protected], [delete]
```

The documentation for this class was generated from the following file:


• internal/classes/singleton.h

# 7.65 qpp::exception::SizeMismatch Class Reference


Size mismatch exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SizeMismatch:



Collaboration diagram for qpp::exception::SizeMismatch:



# **Public Member Functions**

• std::string type\_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

# 7.65.1 Detailed Description

Size mismatch exception.

Sizes do not match

## 7.65.2 Member Function Documentation

## 7.65.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred
-------	--

# 7.65.2.2 type\_description()

```
std::string qpp::exception::SizeMismatch::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

### Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h

# 7.66 qpp::NoiseType::StateDependent Class Reference

Template tag, used whenever the noise is state-dependent.

#include <classes/noise.h>

# 7.66.1 Detailed Description

Template tag, used whenever the noise is state-dependent.

The documentation for this class was generated from the following file:

· classes/noise.h

# 7.67 qpp::NoiseType::StateIndependent Class Reference

Template tag, used whenever the noise is state-independent.

#include <classes/noise.h>

#### 7.67.1 Detailed Description

Template tag, used whenever the noise is state-independent.

The documentation for this class was generated from the following file:


classes/noise.h

# 7.68 qpp::States Class Reference


const Singleton class that implements most commonly used states

#include <classes/states.h>

Inheritance diagram for qpp::States:



Collaboration diagram for qpp::States:



#### **Public Member Functions**

• ket mes (idx d=2) const

Maximally entangled state of 2 qudits.

• ket zero (idx n, idx d=2) const

Zero state of n qudits.

• ket one (idx n, idx d=2) const

One state of n qudits.

• ket jn (idx j, idx n, idx d=2) const

 $|j\rangle^{\otimes n}$  state of n qudits

• ket plus (idx n) const

Plus state of n qubits.

• ket minus (idx n) const

Minus state of n qubits.

#### **Public Attributes**

```
    ket x0 {ket::Zero(2)}
```

Pauli Sigma-X 0-eigenstate |+>

ket x1 {ket::Zero(2)}

Pauli Sigma-X 1-eigenstate |->

ket y0 {ket::Zero(2)}

Pauli Sigma-Y 0-eigenstate |y+>

ket y1 {ket::Zero(2)}

Pauli Sigma-Y 1-eigenstate | y->

ket z0 {ket::Zero(2)}

Pauli Sigma-Z 0-eigenstate | 0>

ket z1 {ket::Zero(2)}

Pauli Sigma-Z 1-eigenstate | 1>

• cmat px0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

• cmat px1 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.

```
    cmat py0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 0-eigenstate |y+\rangle < y+|.

    cmat py1 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.

    cmat pz0 {cmat::Zero(2, 2)}

      Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
• cmat pz1 {cmat::Zero(2, 2)}
      Projector onto the Pauli Sigma-Z 1-eigenstate | 1><1|.
ket b00 {ket::Zero(4)}
      Bell-00 state, as described in Nielsen and Chuang.

    ket b01 {ket::Zero(4)}

      Bell-01 state, as described in Nielsen and Chuang.

    ket b10 {ket::Zero(4)}

      Bell-10 state, as described in Nielsen and Chuang.
ket b11 {ket::Zero(4)}
      Bell-11 state, as described in Nielsen and Chuang.

    cmat pb00 {cmat::Zero(4, 4)}

      Projector onto the Bell-00 state.

    cmat pb01 {cmat::Zero(4, 4)}

      Projector onto the Bell-01 state.

    cmat pb10 {cmat::Zero(4, 4)}

      Projector onto the Bell-10 state.

    cmat pb11 {cmat::Zero(4, 4)}

      Projector onto the Bell-11 state.
ket GHZ {ket::Zero(8)}
      GHZ state.

    ket W {ket::Zero(8)}

      W state.
cmat pGHZ {cmat::Zero(8, 8)}
      Projector onto the GHZ state.
cmat pW {cmat::Zero(8, 8)}
      Projector onto the W state.
```

#### **Private Member Functions**

- States ()
- ∼States ()=default

Default destructor.

#### **Friends**

class internal::Singleton < const States >

#### **Additional Inherited Members**

#### 7.68.1 Detailed Description

const Singleton class that implements most commonly used states

# 7.68.2 Constructor & Destructor Documentation

```
7.68.2.1 States()

qpp::States::States ( ) [inline], [private]

Initialize the states

7.68.2.2 ~States()

qpp::States::~States ( ) [private], [default]
```

# 7.68.3 Member Function Documentation

```
7.68.3.1 jn()
```

Default destructor.

 $|j\rangle^{\otimes n}$  state of *n* qudits

#### **Parameters**

j	Non-negative integer
n	Non-negative integer
d	Subsystem dimensions

# Returns

 $|j\rangle^{\otimes n}$  state of *n* qudits

# 7.68.3.2 mes()

```
ket qpp::States::mes (
idx d = 2 ) const [inline]
```

Maximally entangled state of 2 qudits.

#### **Parameters**

d Subsystem dimensions

#### Returns

Maximally entangled state  $\frac{1}{\sqrt{d}} \sum_{j=0}^{d-1} |jj\rangle$  of 2 qudits

#### 7.68.3.3 minus()

```
ket qpp::States::minus (
          idx n ) const [inline]
```

Minus state of *n* qubits.

#### **Parameters**

n Non-negative integer

#### Returns

Minus state  $|-\rangle^{\otimes n}$  of n qubits

#### 7.68.3.4 one()

```
ket qpp::States::one (
        idx n,
        idx d = 2 ) const [inline]
```

One state of *n* qudits.

#### **Parameters**

n	Non-negative integer
d	Subsystem dimensions

## Returns

One state  $|1\rangle^{\otimes n}$  of n qudits

#### 7.68.3.5 plus()

```
ket qpp::States::plus (
         idx n ) const [inline]
```

Plus state of *n* qubits.

#### **Parameters**

```
n Non-negative integer
```

# Returns

Plus state  $|+\rangle^{\otimes n}$  of n qubits

# 7.68.3.6 zero()

```
ket qpp::States::zero (
         idx n,
         idx d = 2 ) const [inline]
```

Zero state of *n* qudits.

# **Parameters**

n	Non-negative integer
d	Subsystem dimensions

#### Returns

Zero state  $|0\rangle^{\otimes n}$  of n qudits

# 7.68.4 Friends And Related Function Documentation

```
7.68.4.1 internal::Singleton < const States >
```

```
friend class internal::Singleton< const States > [friend]
```

# 7.68.5 Member Data Documentation

```
7.68.5.1 b00
```

```
ket qpp::States::b00 {ket::Zero(4)}
```

Bell-00 state, as described in Nielsen and Chuang.

#### 7.68.5.2 b01

```
ket qpp::States::b01 {ket::Zero(4)}
```

Bell-01 state, as described in Nielsen and Chuang.

#### 7.68.5.3 b10

```
ket qpp::States::b10 {ket::Zero(4)}
```

Bell-10 state, as described in Nielsen and Chuang.

# 7.68.5.4 b11

```
ket qpp::States::b11 {ket::Zero(4)}
```

Bell-11 state, as described in Nielsen and Chuang.

#### 7.68.5.5 GHZ

```
ket qpp::States::GHZ {ket::Zero(8)}
```

GHZ state.

# 7.68.5.6 pb00

```
cmat qpp::States::pb00 {cmat::Zero(4, 4)}
```

Projector onto the Bell-00 state.

```
7.68.5.7 pb01
cmat qpp::States::pb01 {cmat::Zero(4, 4)}
Projector onto the Bell-01 state.
7.68.5.8 pb10
cmat qpp::States::pb10 {cmat::Zero(4, 4)}
Projector onto the Bell-10 state.
7.68.5.9 pb11
cmat qpp::States::pb11 {cmat::Zero(4, 4)}
Projector onto the Bell-11 state.
7.68.5.10 pGHZ
cmat qpp::States::pGHZ {cmat::Zero(8, 8)}
Projector onto the GHZ state.
7.68.5.11 pW
cmat qpp::States::pW {cmat::Zero(8, 8)}
Projector onto the W state.
7.68.5.12 px0
cmat qpp::States::px0 {cmat::Zero(2, 2)}
```

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

```
7.68.5.13 px1
cmat qpp::States::px1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.
7.68.5.14 py0
cmat qpp::States::py0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 0-eigenstate |y+>< y+|.
7.68.5.15 py1
cmat qpp::States::py1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.
7.68.5.16 pz0
cmat qpp::States::pz0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
7.68.5.17 pz1
cmat qpp::States::pz1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 1-eigenstate |1><1|.
7.68.5.18 W
ket qpp::States::W {ket::Zero(8)}
W state.
```

```
7.68.5.19 x0
ket qpp::States::x0 {ket::Zero(2)}
Pauli Sigma-X 0-eigenstate |+>
7.68.5.20 x1
ket qpp::States::x1 {ket::Zero(2)}
Pauli Sigma-X 1-eigenstate |->
7.68.5.21 y0
ket qpp::States::y0 {ket::Zero(2)}
Pauli Sigma-Y 0-eigenstate |y+>
7.68.5.22 y1
ket qpp::States::y1 {ket::Zero(2)}
Pauli Sigma-Y 1-eigenstate |y->
7.68.5.23 z0
ket qpp::States::z0 {ket::Zero(2)}
Pauli Sigma-Z 0-eigenstate |0>
7.68.5.24 z1
ket qpp::States::z1 {ket::Zero(2)}
Pauli Sigma-Z 1-eigenstate |1>
The documentation for this class was generated from the following file:
```


classes/states.h

# 7.69 qpp::exception::SubsysMismatchDims Class Reference


Subsystems mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SubsysMismatchDims:



Collaboration diagram for qpp::exception::SubsysMismatchDims:



#### **Public Member Functions**

• std::string type\_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

# 7.69.1 Detailed Description

Subsystems mismatch dimensions exception.

std::vector<idx> of subsystem labels has duplicates, or has entries that are larger than the size of the std← ::vector<idx> of dimensions

#### 7.69.2 Member Function Documentation

#### 7.69.2.1 Exception()

```
qpp::exception::Exception [inline], [explicit]
```

Constructs an exception.

#### **Parameters**

Text representing where the exception of	П
--	---

#### 7.69.2.2 type\_description()

```
std::string qpp::exception::SubsysMismatchDims::type_description ( ) const [inline], [override],
[virtual]
```

Exception type description.

#### Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.70 qpp::Timer < T, CLOCK\_T > Class Template Reference


Chronometer.

#include <classes/timer.h>

Inheritance diagram for qpp::Timer< T, CLOCK\_T >:



Collaboration diagram for qpp::Timer < T, CLOCK\_T >:



# **Public Member Functions**

· Timer () noexcept

Constructs an instance with the current time as the starting point.

• void tic () noexcept

Resets the chronometer.

• const Timer & toc () noexcept

 ${\it Stops the chronometer.}$ 

· double tics () const noexcept

Time passed in the duration specified by T.

• template<typename U = T>

U get\_duration () const noexcept

Duration specified by U.

• Timer (const Timer &)=default

Default copy constructor.

• Timer (Timer &&)=default

Default move constructor.

• Timer & operator= (const Timer &)=default

Default copy assignment operator.

• Timer & operator= (Timer &&)=default

Default move assignment operator.

virtual ∼Timer ()=default

Default virtual destructor.

#### **Protected Attributes**

- CLOCK\_T::time\_point start\_
- CLOCK\_T::time\_point end\_

#### **Private Member Functions**

 std::ostream & display (std::ostream &os) const override *qpp::IDisplay::display() override*

## 7.70.1 Detailed Description

```
template < typename\ T = std::chrono::duration < double >, typename\ CLOCK\_T = std::chrono::steady\_clock > class\ qpp::Timer < T,\ CLOCK\_T >
```

Chronometer.

## **Template Parameters**

T	Tics duration, default is std::chrono::duration <double, 1="">, i.e. seconds in double precision</double,>
CLOCK← T	Clock's type, default is std::chrono::steady_clock, not affected by wall clock changes during runtime

#### 7.70.2 Constructor & Destructor Documentation

```
7.70.2.1 Timer() [1/3]
```

```
\label{template} $$ \ensuremath{\texttt{template}}$ $$ \ensuremath{\texttt{typename T}} = \ensuremath{\texttt{std}}$ ::chrono::steady $$ $$ $$ $$ $$ \ensuremath{\texttt{clock}}$ $$ $$ \ensuremath{\texttt{qpp}}$ ::Timer ( ) [inline], [noexcept] $$
```

Constructs an instance with the current time as the starting point.

#### **7.70.2.2 Timer()** [2/3]

Default copy constructor.

#### **7.70.2.3 Timer()** [3/3]

Default move constructor.

#### 7.70.2.4 $\sim$ Timer()

```
\label{template} $$ \ensuremath{\sf template}$ $$ \ensurem
```

Default virtual destructor.

#### 7.70.3 Member Function Documentation

#### 7.70.3.1 display()

# qpp::IDisplay::display() override

Writes to the output stream the number of tics (specified by T) that passed between the instantiation/reset and invocation of <a href="mailto:qpp::Timer::toc">qpp::Timer::toc</a>().

#### **Parameters**

```
os Output stream passed by reference
```

#### Returns

Reference to the output stream

Implements qpp::IDisplay.

#### 7.70.3.2 get\_duration()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
template<typename U = T>
U qpp::Timer< T, CLOCK_T >::get_duration ( ) const [inline], [noexcept]
```

Duration specified by U.

#### **Template Parameters**

U Duration, default is T, which defaults to std::chrono::duration<double, 1>, i.e. seconds in double precision

#### Returns

Duration that passed between the instantiation/reset and invocation of qpp::Timer::toc()

```
7.70.3.3 operator=() [1/2]
```

Default copy assignment operator.

```
7.70.3.4 operator=() [2/2]
```

Default move assignment operator.

#### 7.70.3.5 tic()

Resets the chronometer.

Resets the starting/ending point to the current time

#### 7.70.3.6 tics()

```
 \begin{tabular}{ll} template < typename T = std::chrono::duration < double >, typename CLOCK_T = std::chrono::steady \leftarrow \_clock > \\ double qpp::Timer < T, CLOCK_T >::tics ( ) const [inline], [noexcept] \\ \end{tabular}
```

Time passed in the duration specified by T.

#### Returns

Number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc()

## 7.70.3.7 toc()

```
\label{lock-type-ame} $$ $$ template<typename T = std::chrono::steady \leftarrow \_clock> $$ const Timer& qpp::Timer< T, CLOCK_T >::toc ( ) [inline], [noexcept] $$
```

Stops the chronometer.

Set the current time as the ending point

#### Returns

Reference to the current instance

## 7.70.4 Member Data Documentation

#### 7.70.4.1 end

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady←
   _clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::end_ [protected]
```

7.70.4.2 start\_

```
\label{lock_type_name_type_name_type} $$ \end{substitute} $$ $$ \end{substitute} $$
```

The documentation for this class was generated from the following file:


· classes/timer.h

# 7.71 qpp::exception::TypeMismatch Class Reference


Type mismatch exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::TypeMismatch:



Collaboration diagram for qpp::exception::TypeMismatch:



#### **Public Member Functions**

- std::string type\_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

# 7.71.1 Detailed Description

Type mismatch exception.

Scalar types do not match

### 7.71.2 Member Function Documentation

#### 7.71.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

where Text representing where the exception occurred
--

# 7.71.2.2 type\_description()

std::string qpp::exception::TypeMismatch::type\_description ( ) const [inline], [override],
[virtual]

Exception type description.

#### Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.72 qpp::exception::UndefinedType Class Reference


Not defined for this type exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::UndefinedType:



Collaboration diagram for qpp::exception::UndefinedType:



#### **Public Member Functions**

- std::string type\_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

# 7.72.1 Detailed Description

Not defined for this type exception.

Templated specialization is not defined for this type

# 7.72.2 Member Function Documentation

#### 7.72.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred	1
-------	--	---

# 7.72.2.2 type\_description()

std::string qpp::exception::UndefinedType::type\_description ( ) const [inline], [override],
[virtual]

Exception type description.

#### Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


• classes/exception.h

# 7.73 qpp::exception::Unknown Class Reference


Unknown exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Unknown:



Collaboration diagram for qpp::exception::Unknown:



#### **Public Member Functions**

- std::string type\_description () const override Exception type description.
- Exception (const std::string &where)

Constructs an exception.

# 7.73.1 Detailed Description

Unknown exception.

Thrown when no other exception is suitable (not recommended, it is better to define another suitable exception type)

### 7.73.2 Member Function Documentation

#### 7.73.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

where	Text representing where the exception occurred
-------	--

#### 7.73.2.2 type\_description()

std::string qpp::exception::Unknown::type\_description ( ) const [inline], [override], [virtual]
Exception type description.

#### Returns

**Exception** type description


Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

# 7.74 qpp::QCircuit::iterator::value\_type\_ Class Reference

Inheritance diagram for qpp::QCircuit::iterator::value\_type\_:



Collaboration diagram for qpp::QCircuit::iterator::value\_type\_:



#### **Public Member Functions**

```
    value_type_ (const QCircuit *value_type_qcd)
    Default value_type_ constructor.
```

• value\_type\_ (const value\_type\_ &)=default

Default copy constructor.

value\_type\_ & operator= (const value\_type\_ &)=default
 Default copy assignment operator.

#### **Public Attributes**

```
• const QCircuit * value_type_qcd_
```

< non-owning pointer to the parent iterator

StepType type\_{StepType::NONE}

step type

• idx ip\_ {idx\_infty}

instruction pointer

std::vector< GateStep >::const\_iterator gates\_ip\_ {}

gates instruction pointer

std::vector< MeasureStep >::const\_iterator measurements\_ip\_ {}

measurements instruction pointer

#### **Private Member Functions**

## 7.74.1 Constructor & Destructor Documentation

Default value\_type\_ constructor.

#### **Parameters**

```
7.74.1.2 value_type_() [2/2]

qpp::QCircuit::iterator::value_type_::value_type_ (
```

```
const value_type_ & ) [default]
```

Default copy constructor.

#### 7.74.2 Member Function Documentation

```
7.74.2.1 display()
```

qpp::IDisplay::display() override

Writes to the output stream the textual representation of the iterator de-referenced element

#### **Parameters**

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

#### 7.74.2.2 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

### 7.74.3 Member Data Documentation

```
7.74.3.1 gates_ip_
std::vector<GateStep>::const_iterator qpp::QCircuit::iterator::value_type_::gates_ip_ {}
gates instruction pointer
```

```
7.74.3.2 ip_
idx qpp::QCircuit::iterator::value_type_::ip_ {idx_infty}
instruction pointer
7.74.3.3 measurements_ip_
\verb|std::vector<| MeasureStep| > ::const_iterator | qpp::QCircuit::iterator::value_type_::measurements\_{\leftarrow}| | qpp::QCircuit::qt_iterator::value_type_::qt_iterator::value_type_::qt_iterator::value_type_::qt_iterator::value_type_::qt_iterator::value_type_::qt_iterator::value_type_::qt_iterator::value_type_:
ip_ {}
measurements instruction pointer
7.74.3.4 type_
StepType qpp::QCircuit::iterator::value_type_::type_ {StepType::NONE}
step type
7.74.3.5 value_type_qcd_
const QCircuit* qpp::QCircuit::iterator::value_type_::value_type_qcd_
 < non-owning pointer to the parent iterator
The documentation for this class was generated from the following file:
```

Generated by Doxygen


· classes/circuits.h

# 7.75 qpp::exception::ZeroSize Class Reference


Object has zero size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::ZeroSize:



Collaboration diagram for qpp::exception::ZeroSize:



#### **Public Member Functions**

• std::string type\_description () const override

Exception type description.

• Exception (const std::string &where)

Constructs an exception.

# 7.75.1 Detailed Description

Object has zero size exception.

Zero sized object, e.g. empty Eigen::Matrix or std::vector with no elements

#### 7.75.2 Member Function Documentation

#### 7.75.2.1 Exception()

qpp::exception::Exception [inline], [explicit]

Constructs an exception.

#### **Parameters**

where Text representing where the exception occurred

#### 7.75.2.2 type\_description()

std::string qpp::exception::ZeroSize::type\_description ( ) const [inline], [override], [virtual]

Exception type description.

#### Returns

**Exception** type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h


# **Chapter 8**

# **File Documentation**

# 8.1 classes/circuits.h File Reference

Support for qudit quantum circuits.

This graph shows which files directly or indirectly include this file:



# Classes

· class qpp::QCircuit

Quantum circuit class.

• struct qpp::QCircuit::GateStep

One step consisting only of gates/operators in the circuit.

struct qpp::QCircuit::MeasureStep

One step consisting only of measurements in the circuit.

· class qpp::QCircuit::iterator

Quantum circuit bound-checking (safe) iterator.

- class qpp::QCircuit::iterator::value\_type\_
- class qpp::QEngine

Quantum circuit engine, executes qpp::QCircuit.

356 File Documentation

# **Namespaces**

• qpp

Quantum++ main namespace.


# 8.1.1 Detailed Description

Support for qudit quantum circuits.

# 8.2 classes/codes.h File Reference

Quantum error correcting codes.

This graph shows which files directly or indirectly include this file:



### **Classes**

· class qpp::Codes

const Singleton class that defines quantum error correcting codes

# **Namespaces**

• qpp

Quantum++ main namespace.


# 8.2.1 Detailed Description

Quantum error correcting codes.

# 8.3 classes/exception.h File Reference

Exceptions.

This graph shows which files directly or indirectly include this file:



#### **Classes**

• class qpp::exception::Exception

Base class for generating Quantum++ custom exceptions.

· class qpp::exception::Unknown

Unknown exception.

class qpp::exception::ZeroSize

Object has zero size exception.

• class qpp::exception::MatrixNotSquare

Matrix is not square exception.

class qpp::exception::MatrixNotCvector

Matrix is not a column vector exception.

· class qpp::exception::MatrixNotRvector

Matrix is not a row vector exception.

class qpp::exception::MatrixNotVector

Matrix is not a vector exception.

class qpp::exception::MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

• class qpp::exception::MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

· class qpp::exception::MatrixNotSquareNorVector

Matrix is not square nor vector exception.

class qpp::exception::MatrixMismatchSubsys

Matrix mismatch subsystems exception.

· class qpp::exception::DimsInvalid

Invalid dimension(s) exception.

class qpp::exception::DimsNotEqual

Dimensions not equal exception.

class qpp::exception::DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

class qpp::exception::DimsMismatchCvector

358 File Documentation

Dimension(s) mismatch column vector size exception.

· class qpp::exception::DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

class qpp::exception::DimsMismatchVector

Dimension(s) mismatch vector size exception.

class qpp::exception::SubsysMismatchDims

Subsystems mismatch dimensions exception.

· class qpp::exception::PermInvalid

Invalid permutation exception.

class qpp::exception::PermMismatchDims

Permutation mismatch dimensions exception.

· class qpp::exception::NotQubitMatrix

Matrix is not 2 x 2 exception.

class qpp::exception::NotQubitCvector

Column vector is not 2 x 1 exception.

class qpp::exception::NotQubitRvector

Row vector is not 1 x 2 exception.

class qpp::exception::NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

• class qpp::exception::NotQubitSubsys

Subsystems are not qubits exception.

· class qpp::exception::NotBipartite

Not bi-partite exception.

· class qpp::exception::NoCodeword

Codeword does not exist exception.

· class qpp::exception::OutOfRange

Argument out of range exception.

· class qpp::exception::TypeMismatch

Type mismatch exception.

• class qpp::exception::SizeMismatch

Size mismatch exception.

class qpp::exception::UndefinedType

Not defined for this type exception.

· class qpp::exception::QuditAlreadyMeasured

Qudit was already measured exception.

· class qpp::exception::Duplicates

System (e.g. std::vector) has duplicates exception.

· class qpp::exception::CustomException

Custom exception.

· class qpp::exception::NotImplemented

Code not yet implemented.

· class qpp::exception::InvalidIterator

Invalid iterator.

#### **Namespaces**

qpp

Quantum++ main namespace.

• qpp::exception

Quantum++ exception hierarchy namespace.


# 8.3.1 Detailed Description

Exceptions.

# 8.4 classes/gates.h File Reference

Quantum gates.

This graph shows which files directly or indirectly include this file:



# **Classes**

• class qpp::Gates

const Singleton class that implements most commonly used gates

# **Namespaces**

• qpp

Quantum++ main namespace.

# 8.4.1 Detailed Description


Quantum gates.

360 File Documentation

# 8.5 classes/idisplay.h File Reference

Display interface via the non-virtual interface (NVI) and very basic JSON serialization support interface.

This graph shows which files directly or indirectly include this file:



#### **Classes**

· class qpp::IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

class qpp::IJSON

Abstract class (interface) that mandates the definition of very basic JSON serialization support.

#### **Namespaces**

• qpp

Quantum++ main namespace.


# 8.5.1 Detailed Description

Display interface via the non-virtual interface (NVI) and very basic JSON serialization support interface.

# 8.6 classes/init.h File Reference

Initialization.

This graph shows which files directly or indirectly include this file:



#### Classes

· class qpp::Init

const Singleton class that performs additional initializations/cleanups

#### **Namespaces**

• qpp

Quantum++ main namespace.


# 8.6.1 Detailed Description

Initialization.

## 8.7 classes/noise.h File Reference

Noise models.

This graph shows which files directly or indirectly include this file:



#### **Classes**

· class qpp::NoiseType

Contains template tags used to specify the noise type.

class qpp::NoiseBase< T >

Base class for all noise models, derive your particular noise model.

class qpp::QubitDepolarizingNoise

Qubit depolarizing noise.

· class qpp::QubitPhaseFlipNoise

Qubit phase flip (dephasing) noise.

· class qpp::QubitBitFlipNoise

Qubit bit flip noise.

· class qpp::QubitBitPhaseFlipNoise

Qubit bit-phase flip (dephasing) noise.

· class qpp::QubitAmplitudeDampingNoise

Qubit amplitude damping noise, as described in Nielsen and Chuang.

· class qpp::QubitPhaseDampingNoise

Qubit phase damping noise, as described in Nielsen and Chuang.

· class qpp::QuditDepolarizingNoise

Qudit depolarizing noise.

# **Namespaces**

• qpp

Quantum++ main namespace.


# 8.7.1 Detailed Description

Noise models.

# 8.8 classes/random\_devices.h File Reference

Random devices.

This graph shows which files directly or indirectly include this file:



#### Classes

• class qpp::RandomDevices

Singleton class that manages the source of randomness in the library.

# **Namespaces**

• qpp

Quantum++ main namespace.


# 8.8.1 Detailed Description

Random devices.

# 8.9 classes/reversible.h File Reference

Support for classical reversible circuits.

This graph shows which files directly or indirectly include this file:



#### **Classes**

class qpp::Dynamic\_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

class qpp::Bit\_circuit

Classical reversible circuit simulator.

• struct qpp::Bit\_circuit::Gate\_count

## **Namespaces**

qpp

Quantum++ main namespace.


# 8.9.1 Detailed Description

Support for classical reversible circuits.

# 8.10 classes/states.h File Reference

Quantum states.

This graph shows which files directly or indirectly include this file:



# **Classes**

• class qpp::States

const Singleton class that implements most commonly used states

# **Namespaces**

• qpp

Quantum++ main namespace.


# 8.10.1 Detailed Description

Quantum states.

# 8.11 classes/timer.h File Reference

Timing.

This graph shows which files directly or indirectly include this file:



#### Classes

class qpp::Timer < T, CLOCK\_T >
 Chronometer.

# **Namespaces**

• qpp

Quantum++ main namespace.


## 8.11.1 Detailed Description

Timing.

## 8.12 constants.h File Reference

Constants.

This graph shows which files directly or indirectly include this file:



# **Namespaces**

• qpp

Quantum++ main namespace.

• qpp::literals

#### **Functions**

- constexpr cplx qpp::literals::operator"" \_i (unsigned long long int x) noexcept User-defined literal for complex  $i=\sqrt{-1}$  (integer overload)
- constexpr cplx qpp::operator"" \_i (long double x) noexcept

User-defined literal for complex  $i = \sqrt{-1}$  (real overload)

• cplx qpp::omega (idx D)

D-th root of unity.

#### **Variables**

• constexpr double <a href="mailto:qpp::chop">qpp::chop</a> = 1e-10

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

• constexpr double <a href="mailto:qpp::eps">qpp::eps</a> = std::numeric\_limits<double>::epsilon()

Used to decide whether a number or expression in double precision is zero or not for the purpose of a specific computation.

• constexpr idx qpp::maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

• constexpr double qpp::pi = 3.141592653589793238462643383279502884

• constexpr double qpp::ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

constexpr double <a href="mailto:qpp::infty">qpp::infty</a> = std::numeric\_limits<double>::max()

Used to denote infinity in double precision.

• const idx qpp::idx\_infty = static\_cast<idx>(-1)

Used to denote the largest unsigned index.


#### 8.12.1 Detailed Description

Constants.

# 8.13 entanglement.h File Reference

Entanglement functions.

This graph shows which files directly or indirectly include this file:



## **Namespaces**

• qpp

Quantum++ main namespace.

#### **Functions**

```
    template<typename Derived >

  dyn col vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector<
  idx > &dims)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  dyn_col_vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  cmat qpp::schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat qpp::schmidtA (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Bob side.

    template<typename Derived >

  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Bob side.
• template<typename Derived >
  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx
  > &dims)
      Schmidt probabilities of the bi-partite pure state A.

    template<typename Derived >

  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt probabilities of the bi-partite pure state A.
• template<typename Derived >
  double qpp::entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Entanglement of the bi-partite pure state A.
• template<typename Derived >
  double <a href="mailto:qpp::entanglement">qpp::entanglement</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Entanglement of the bi-partite pure state A.

    template<typename Derived >

  double <a href="mailto:qpp::gconcurrence">qpp::gconcurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      G-concurrence of the bi-partite pure state A.

    template<typename Derived >

  double qpp::negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double <a href="mailto:qpp::negativity">qpp::negativity</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double <a href="mailto:qpp::concurrence">qpp::concurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.
```


#### 8.13.1 Detailed Description

Entanglement functions.

# 8.14 entropies.h File Reference

Entropy functions.

This graph shows which files directly or indirectly include this file:



#### **Namespaces**

• qpp

Quantum++ main namespace.

#### **Functions**

```
    template < typename Derived >
        double qpp::entropy (const Eigen::MatrixBase < Derived > &A)
```

von-Neumann entropy of the density matrix A

double qpp::entropy (const std::vector< double > &prob)

Shannon entropy of the probability distribution prob.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$ 

```
double <a href="mailto:qpp::renyi">qpp::renyi</a> (const Eigen::MatrixBase< Derived > &A, double alpha)
```

Renyi- $\alpha$  entropy of the density matrix A, for  $\alpha \geq 0$ .

double <a href="mailto:qpp::renyi">qpp::renyi</a> (const std::vector< double > &prob, double alpha)

Renyi-  $\alpha$  entropy of the probability distribution prob, for  $\alpha \geq 0$ .

template<typename Derived >

```
double <a href="mailto:qpp::tsallis">qpp::tsallis</a> (const Eigen::MatrixBase< Derived > &A, double q)
```

Tsallis- q entropy of the density matrix A, for  $q \geq 0$ .

double qpp::tsallis (const std::vector< double > &prob, double q)

Tsallis- q entropy of the probability distribution prob, for  $q \geq 0$ .

• template<typename Derived >

double qpp::qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const std::vector< idx > &subsysB, const std::vector< idx > &dims)

Quantum mutual information between 2 subsystems of a composite system.

• template<typename Derived >

 $\label{lem:double qpp::qmutualinfo} $$ double qpp::qmutualinfo (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &subsysA, const std::vector < idx > &subsysB, idx d=2) $$$ 

Quantum mutual information between 2 subsystems of a composite system.

# 8.14.1 Detailed Description

Entropy functions.

# 8.15 experimental/experimental.h File Reference

Experimental/test functions/classes.

## **Namespaces**

• qpp

Quantum++ main namespace.

· qpp::experimental

Experimental/test functions/classes, do not use or modify.


# 8.15.1 Detailed Description

Experimental/test functions/classes.

# 8.16 functions.h File Reference

Generic quantum computing functions.

This graph shows which files directly or indirectly include this file:



# **Namespaces**

• qpp

Quantum++ main namespace.

qpp::literals

#### **Functions**

```
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::transpose (const Eigen::MatrixBase< Derived > &A)
• template<typename Derived >
  dyn mat< typename Derived::Scalar > qpp::conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::adjoint (const Eigen::MatrixBase< Derived > &A)
      Adjoint.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::inverse (const Eigen::MatrixBase< Derived > &A)
      Inverse.

    template<typename Derived >

  Derived::Scalar qpp::trace (const Eigen::MatrixBase < Derived > &A)
• template<typename Derived >
  Derived::Scalar <a href="mailto:qpp::det">qpp::det</a> (const Eigen::MatrixBase</a> Derived > &A)

    template<typename Derived >

  Derived::Scalar qpp::logdet (const Eigen::MatrixBase< Derived > &A)
     Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar <a href="mailto:qpp::sum">qpp::sum</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise sum of A.
template<typename Derived >
  Derived::Scalar <a href="mailto:open:prod">open:prod</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise product of A.
• template<typename Derived >
  double <a href="mailto:qpp::norm">qpp::norm</a> (const Eigen::MatrixBase< Derived > &A)
      Frobenius norm.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::normalize (const Eigen::MatrixBase< Derived > &A)
      Normalizes state vector (column or row vector) or density matrix.
• template<typename Derived >
  std::pair< dyn_col_vect< cplx >, cmat > qpp::eig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition.
• template<typename Derived >
  dyn_col_vect< cplx > qpp::evals (const Eigen::MatrixBase< Derived > &A)
     Eigenvalues.

    template<typename Derived >

  cmat qpp::evects (const Eigen::MatrixBase< Derived > &A)
      Eigenvectors.

    template<typename Derived >

  std::pair< dyn_col_vect< double >, cmat > qpp::heig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > qpp::hevals (const Eigen::MatrixBase< Derived > &A)
      Hermitian eigenvalues.
ullet template<typename Derived >
  cmat qpp::hevects (const Eigen::MatrixBase< Derived > &A)
      Eigenvectors of Hermitian matrix.
```

```
• template<typename Derived >
  std::tuple< cmat, dyn_col_vect< double >, cmat > qpp::svd (const Eigen::MatrixBase< Derived > &A)
     Full singular value decomposition.

    template<typename Derived >

  dyn_col_vect< double > qpp::svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.
• template<typename Derived >
  cmat qpp::svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.

    template<typename Derived >

  cmat qpp::svdV (const Eigen::MatrixBase< Derived > &A)
     Right singular vectors.

    template<typename Derived >

  cmat qpp::funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)

    template < typename Derived >

  cmat qpp::sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.
• template<typename Derived >
  cmat qpp::absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.

    template<typename Derived >

  cmat qpp::expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.
• template<typename Derived >
  cmat qpp::logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.
• template<typename Derived >
  cmat <a href="mailto:qpp::sinm">qpp::sinm</a> (const Eigen::MatrixBase</a> Derived > &A)
     Matrix sin.
• template<typename Derived >
  cmat qpp::cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.
• template<typename Derived >
  cmat qpp::spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.
template<typename Derived >
  dyn mat< typename Derived::Scalar > qpp::powm (const Eigen::MatrixBase< Derived > &A, idx n)
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

    template<typename Derived >

  double qpp::schatten (const Eigen::MatrixBase< Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > qpp::cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const
  typename Derived::Scalar &))
     Functor.
• template<typename T >
  dyn_mat< typename T::Scalar > qpp::kron (const T &head)
     Kronecker product.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > qpp::kron (const T &head, const Args &... tail)
     Kronecker product.
```

```
    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::kron (const std::vector< Derived > &As)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::kron (const std::initializer list< Derived > &As)
     Kronecker product.
template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Kronecker power.
• template<typename T >
  dyn_mat< typename T::Scalar > qpp::dirsum (const T &head)
     Direct sum.
• template<typename T , typename... Args>
  dyn mat< typename T::Scalar > qpp::dirsum (const T &head, const Args &... tail)
     Direct sum.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::vector< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::initializer_list< Derived > &As)
     Direct sum.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::reshape (const Eigen::MatrixBase< Derived > &A, idx rows,
  idx cols)
     Reshape.

    template < typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > qpp::comm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Commutator.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > qpp::anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::prj (const Eigen::MatrixBase< Derived > &A)
     Projector.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::grams (const std::vector< Derived > &As)
     Gram-Schmidt orthogonalization.
template<typename Derived >
  dyn mat< typename Derived::Scalar > qpp::grams (const std::initializer list< Derived > &As)
     Gram-Schmidt orthogonalization.
• template<typename Derived >
  dyn mat< typename Derived::Scalar > qpp::grams (const Eigen::MatrixBase< Derived > &A)
     Gram-Schmidt orthogonalization.

    std::vector< idx > qpp::n2multiidx (idx n, const std::vector< idx > &dims)

     Non-negative integer index to multi-index.

    idx qpp::multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

     Multi-index to non-negative integer index.

    ket qpp::mket (const std::vector< idx > &mask, const std::vector< idx > &dims)
```

Multi-partite qudit ket.

ket qpp::mket (const std::vector< idx > &mask, idx d=2)

Multi-partite qudit ket.

cmat qpp::mprj (const std::vector< idx > &mask, const std::vector< idx > &dims)

Projector onto multi-partite qudit ket.

cmat qpp::mprj (const std::vector < idx > &mask, idx d=2)

Projector onto multi-partite qudit ket.

template<typename InputIterator >

```
std::vector< double > qpp::abssq (InputIterator first, InputIterator last)
```

Computes the absolute values squared of an STL-like range of complex numbers.

template<typename Container >

```
std::vector< double > qpp::abssq (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)
```

Computes the absolute values squared of an STL-like container.

template<typename Derived >

```
std::vector< double > qpp::abssq (const Eigen::MatrixBase< Derived > &A)
```

Computes the absolute values squared of an Eigen expression.

• template<typename InputIterator >

```
std::iterator_traits< InputIterator >::value_type qpp::sum (InputIterator first, InputIterator last)
```

Element-wise sum of an STL-like range.

template<typename Container >

```
Container::value_type qpp::sum (const Container &c, typename std::enable_if< is_iterable< Container >
::value >::type *=nullptr)
```

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

```
std::iterator_traits< InputIterator >::value_type qpp::prod (InputIterator first, InputIterator last)
```

Element-wise product of an STL-like range.

template<typename Container >

```
Container::value_type qpp::prod (const Container &c, typename std::enable_if< is_iterable< Container >
::value >::type *=nullptr)
```

Element-wise product of the elements of an STL-like container.

• template<typename Derived >

```
dyn_col_vect< typename Derived::Scalar > qpp::rho2pure (const Eigen::MatrixBase< Derived > &A)
```

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

• std::vector< idx > qpp::complement (std::vector< idx > subsys, idx n)

Constructs the complement of a subsystem vector.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$ 

```
std::vector< double > qpp::rho2bloch (const Eigen::MatrixBase< Derived > &A)
```

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat qpp::bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

template<char... Bits>

```
ket qpp::literals::operator"" _ket ()
```

Multi-partite qubit ket user-defined literal.

• template<char... Bits>

```
bra qpp::literals::operator"" _bra ()
```

Multi-partite qubit bra user-defined literal.

• template<char... Bits>

```
cmat qpp::literals::operator"" _prj ()
```

Multi-partite qubit projector user-defined literal.


# 8.16.1 Detailed Description

Generic quantum computing functions.

## 8.17 input output.h File Reference

Input/output functions.

This graph shows which files directly or indirectly include this file:



#### **Namespaces**

• qpp

Quantum++ main namespace.

#### **Functions**

template<typename Derived >
 internal::IOManipEigen qpp::disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
 Eigen expression ostream manipulator.

internal::IOManipEigen qpp::disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

• template<typename InputIterator >

internal::IOManipRange< InputIterator > qpp::disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")

Range ostream manipulator.

• template<typename Container >

internal::IOManipRange< typename Container::const\_iterator > qpp::disp (const Container &c, const std⇔ ::string &separator, const std::string &start="[", const std::string &end="]", typename std::enable\_if< is\_⇔ iterable< Container >::value >::type \*=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

• template<typename PointerType >

internal::IOManipPointer< PointerType > qpp::disp (const PointerType \*p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")

C-style pointer ostream manipulator.

• template<typename Derived >

void qpp::save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.


#### 8.17.1 Detailed Description

Input/output functions.

## 8.18 instruments.h File Reference

Measurement functions.

This graph shows which files directly or indirectly include this file:



#### **Namespaces**

• qpp

Quantum++ main namespace.

#### **Functions**

template<typename Derived >
 dyn\_col\_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)
 Generalized inner product.

template<typename Derived >

dyn\_col\_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

ullet template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer\_list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >
 std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase
 Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template < typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer\_list< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer\_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > qpp::measure\_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > qpp::measure\_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, idx d=2)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.


#### 8.18.1 Detailed Description

Measurement functions.

# 8.19 internal/classes/iomanip.h File Reference

Input/output manipulators.

This graph shows which files directly or indirectly include this file:



#### Classes

- class qpp::internal::IOManipRange< InputIterator >
- class qpp::internal::IOManipPointer< PointerType >
- class qpp::internal::IOManipEigen

## **Namespaces**

- qpp
  - Quantum++ main namespace.
- qpp::internal

Internal utility functions, do not use them directly or modify them.


## 8.19.1 Detailed Description

Input/output manipulators.

# 8.20 internal/classes/singleton.h File Reference

Singleton pattern via CRTP.

This graph shows which files directly or indirectly include this file:



#### Classes

class qpp::internal::Singleton< T >

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

## **Namespaces**

• qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


# 8.20.1 Detailed Description

Singleton pattern via CRTP.

# 8.21 internal/util.h File Reference

Internal utility functions.

This graph shows which files directly or indirectly include this file:



#### **Classes**

struct qpp::internal::Display\_Impl\_

## **Namespaces**

qpp

Quantum++ main namespace.

· qpp::internal

Internal utility functions, do not use them directly or modify them.

#### **Functions**

- void qpp::internal::n2multiidx (idx n, idx numdims, const idx \*const dims, idx \*result) noexcept
- idx qpp::internal::multiidx2n (const idx \*const midx, idx numdims, const idx \*const dims) noexcept
- $\bullet \ \ {\it template}{<} {\it typename Derived} >$

bool qpp::internal::check\_square\_mat (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$ 

bool qpp::internal::check\_vector (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check\_rvector (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check cvector (const Eigen::MatrixBase< Derived > &A)

• template<typename T >

bool qpp::internal::check nonzero size (const T &x) noexcept

• template<typename T1 , typename T2 >

bool qpp::internal::check\_matching\_sizes (const T1 &lhs, const T2 &rhs) noexcept

- bool qpp::internal::check dims (const std::vector < idx > &dims)
- template<typename Derived >

bool qpp::internal::check\_dims\_match\_mat (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check\_dims\_match\_cvect (const std::vector < idx > &dims, const Eigen::MatrixBase < Derived > &A)

template<typename Derived >

bool qpp::internal::check\_dims\_match\_rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- bool qpp::internal::check eq dims (const std::vector < idx > &dims, idx dim) noexcept
- bool app::internal::check no duplicates (std::vector< idx > v)
- bool qpp::internal::check\_subsys\_match\_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)
- $\bullet \ \ \text{template}{<} \text{typename Derived} >$

 $bool\ qpp::internal::check\_qubit\_matrix\ (const\ Eigen::MatrixBase < Derived > \&A)\ no except$ 

 $\bullet \ \ \mathsf{template} \mathord{<} \mathsf{typename} \ \mathsf{Derived} >$ 

bool qpp::internal::check\_qubit\_cvector (const Eigen::MatrixBase< Derived > &A) noexcept

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$ 

 $bool\ qpp::internal::check\_qubit\_rvector\ (const\ Eigen::MatrixBase < Derived > \&A)\ noexcept$ 

- $\bullet \ \ \mathsf{template} \mathord{<} \mathsf{typename} \ \mathsf{Derived} >$ 
  - bool qpp::internal::check\_qubit\_vector (const Eigen::MatrixBase< Derived > &A) noexcept
- bool qpp::internal::check\_perm (const std::vector< idx > &perm)
- template<typename Derived1 , typename Derived2 >

dyn\_mat< typename Derived1::Scalar > qpp::internal::kron2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::MatrixBase< Derived2 > &B)

• template<typename Derived1 , typename Derived2 >

dyn\_mat< typename Derived1::Scalar > qpp::internal::dirsum2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::MatrixBase< Derived2 > &B)

• template<typename T >

void qpp::internal::variadic\_vector\_emplace (std::vector< T > &)

- template<typename T , typename First , typename... Args>
  - $\label{eq:condition} \mbox{void qpp::internal::variadic\_vector\_emplace} \mbox{ (std::vector< $T > \&v$, First \&\&first, Args \&\&... args) } \\$
- idx qpp::internal::get\_num\_subsys (idx D, idx d)
- idx qpp::internal::get\_dim\_subsys (idx sz, idx N)

#### 8.21.1 Detailed Description

Internal utility functions.

#### 8.22 MATLAB/matlab.h File Reference

Input/output interfacing with MATLAB.

```
#include "mat.h"
#include "mex.h"
```

## **Namespaces**

• qpp

Quantum++ main namespace.

#### **Functions**

template<typename Derived >
 std::enable\_if< std::is\_same< typename Derived::Scalar, cplx >::value, dyn\_mat< cplx > ::type
 qpp::loadMATLAB (const std::string &mat\_file, const std::string &var\_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable\_if<!std::is\_same< typename Derived::Scalar, cplx >::value, dyn\_mat< typename Derived::

Scalar > >::type qpp::loadMATLAB (const std::string &mat\_file, const std::string &var\_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >
 std::enable\_if< std::is\_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat\_file, const std::string &var\_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

• template<typename Derived >

std::enable\_if< !std::is\_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat\_file, const std::string &var\_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.


#### 8.22.1 Detailed Description

Input/output interfacing with MATLAB.

# 8.23 number\_theory.h File Reference

Number theory functions.

This graph shows which files directly or indirectly include this file:



#### **Namespaces**

• qpp

Quantum++ main namespace.

#### **Functions**

std::vector< int > qpp::x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double qpp::contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

• bigint qpp::gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint qpp::gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint qpp::lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint qpp::lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > qpp::invperm (const std::vector< idx > &perm)

Inverse permutation.

 $\bullet \; \mathsf{std} :: \mathsf{vector} < \mathsf{idx} > \mathsf{qpp} :: \mathsf{compperm} \; (\mathsf{const} \; \mathsf{std} :: \mathsf{vector} < \mathsf{idx} > \& \mathsf{perm}, \; \mathsf{const} \; \mathsf{std} :: \mathsf{vector} < \mathsf{idx} > \& \mathsf{sigma}) \\$ 

Compose permutations.

std::vector< bigint > qpp::factors (bigint a)

Prime factor decomposition.

• bigint <a href="mailto:qpp::modmul">qpp::modmul</a> (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

• bigint qpp::modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

• std::tuple< bigint, bigint, bigint > qpp::egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint qpp::modinv (bigint a, bigint p)

Modular inverse of a mod p.

bool qpp::isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

• bigint qpp::randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

- std::vector< std::pair< int, int > > qpp::convergents (const std::vector< int > &cf)
   Convergents.
- std::vector< std::pair< int, int > > qpp::convergents (double x, idx N)
   Convergents.


#### 8.23.1 Detailed Description

Number theory functions.

# 8.24 operations.h File Reference

Quantum operation functions.

This graph shows which files directly or indirectly include this file:



## **Namespaces**

qpp

Quantum++ main namespace.

# **Functions**

template<typename Derived1 , typename Derived2 >
 dyn\_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 const std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >
 dyn\_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 idx d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn\_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn\_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

• template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std $\leftrightarrow$  ::vector< idx > &target, const std::vector< idx > &dims)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

template<typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std 
::vector< idx > &target, idx d=2)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat qpp::kraus2super (const std::vector< cmat > &Ks)

Superoperator matrix.

cmat qpp::kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector< cmat > qpp::choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat qpp::choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat qpp::super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$ 

dyn\_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

template<typename Derived >

 $\label{lem:dyn_mat} $$ dyn_mat< typename\ Derived::Scalar > qpp::ptrace2\ (const\ Eigen::MatrixBase<\ Derived > \&A,\ const\ std \mapsto ::vector < idx > \&dims) $$$ 

Partial trace.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$ 

Partial trace.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::ptrace (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial trace.

• template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Partial transpose.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2)

Partial transpose.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &perm, const std::vector< idx > &dims)

Subsystem permutation.

template<typename Derived >

 $dyn_mat < typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &perm, idx d=2)$ 

Subsystem permutation.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::applyQFT (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn\_mat< typename Derived::Scalar > qpp::applyTFQ (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

dyn\_col\_vect< typename Derived::Scalar > qpp::TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

• template<typename Derived >

 $dyn\_col\_vect< typename Derived::Scalar > qpp::QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)$ 

Qudit quantum Fourier transform.

#### 8.24.1 Detailed Description

Quantum operation functions.

# 8.25 qpp.h File Reference

Quantum++ main header file, includes all other necessary headers.

```
#include <algorithm>
#include <cassert>
#include <chrono>
#include <cmath>
#include <complex>
#include <cstdlib>
#include <cstring>
#include <exception>
#include <fstream>
```

```
#include <functional>
#include <initializer_list>
#include <iomanip>
#include <iterator>
#include <limits>
#include <memory>
#include <numeric>
#include <ostream>
#include <random>
#include <sstream>
#include <stdexcept>
#include <string>
#include <tuple>
#include <type_traits>
#include <unordered_map>
#include <utility>
#include <vector>
#include <Eigen/Dense>
#include <Eigen/SVD>
#include "types.h"
#include "classes/exception.h"
#include "constants.h"
#include "traits.h"
#include "classes/idisplay.h"
#include "internal/util.h"
#include "internal/classes/iomanip.h"
#include "input_output.h"
#include "internal/classes/singleton.h"
#include "classes/random_devices.h"
#include "random.h"
#include "number_theory.h"
#include "functions.h"
#include "classes/init.h"
#include "classes/codes.h"
#include "classes/gates.h"
#include "classes/states.h"
#include "statistics.h"
#include "operations.h"
#include "entropies.h"
#include "entanglement.h"
#include "classes/timer.h"
#include "instruments.h"
#include "classes/reversible.h"
#include "classes/noise.h"
#include "classes/circuits.h"
```

#### **Namespaces**

qpp

Quantum++ main namespace.

## **Macros**

#define QPP\_UNUSED\_

# 8.25.1 Detailed Description

Quantum++ main header file, includes all other necessary headers.

#### 8.25.2 Macro Definition Documentation


8.25.2.1 QPP\_UNUSED\_

#define QPP\_UNUSED\_

# 8.26 random.h File Reference

Randomness-related functions.

This graph shows which files directly or indirectly include this file:



# **Namespaces**

• qpp

Quantum++ main namespace.

#### **Functions**

double <a href="mailto:qpp::rand">qpp::rand</a> (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

bigint qpp::rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx qpp::randidx (idx a=std::numeric\_limits < idx >::min(), idx b=std::numeric\_limits < idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

template<typename Derived >

Derived <a href="mailto:qpp::rand">qpp::rand</a> (idx rows, idx cols, double a=0, double b=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

template<>

dmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

template<>

cmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived <a href="mailto:qpp::randn">qpp::randn</a> (idx rows, idx cols, double mean=0, double sigma=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

dmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

template<>

cmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

• double qpp::randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

cmat qpp::randU (idx D=2)

Generates a random unitary matrix.

• cmat qpp::randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > qpp::randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat qpp::randH (idx D=2)

Generates a random Hermitian matrix.

ket qpp::randket (idx D=2)

Generates a random normalized ket (pure state vector)

cmat qpp::randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > qpp::randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > qpp::randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.


#### 8.26.1 Detailed Description

Randomness-related functions.

#### 8.27 statistics.h File Reference

Statistics functions.

This graph shows which files directly or indirectly include this file:



#### **Namespaces**

• qpp

Quantum++ main namespace.

#### **Functions**

std::vector< double > qpp::uniform (idx N)

Uniform probability distribution vector.

std::vector< double > qpp::marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > qpp::marginalY (const dmat &probXY)

Marginal distribution.

• template<typename Container >

double qpp::avg (const std::vector< double > &prob, const Container &X, typename std::enable\_if< is\_← iterable< Container >::value >::type \*=nullptr)

Average.

• template<typename Container >

double <a href="mailto:qpp::cov">qpp::cov</a> (const dmat &probXY, const Container &X, const Container &Y, typename std::enable\_if< is\_iterable< Container >::value >::type \*=nullptr)

Covariance.

• template<typename Container >

 $\label{lem:const} \mbox{double qpp::var (const std::vector< double > \&prob, const Container \&X, typename std::enable_if< is\_ & iterable< Container >::value >::type *=nullptr) \\$ 

Variance.

• template<typename Container >

double qpp::sigma (const std::vector< double > &prob, const Container &X, typename std::enable\_if< is\_ $\leftarrow$  iterable< Container >::value >::type \*=nullptr)

Standard deviation.

• template<typename Container >

 $\label{local-container} \begin{tabular}{ll} double & qpp::cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if < is_iterable < Container >::value >::type *=nullptr) \end{tabular}$ 

Correlation.

8.28 traits.h File Reference 389


#### 8.27.1 Detailed Description

Statistics functions.

## 8.28 traits.h File Reference

Type traits.

This graph shows which files directly or indirectly include this file:



## Classes

struct qpp::make\_void< Ts >

Helper for qpp::to\_void<> alias template.

struct qpp::is\_iterable < T, typename >

Checks whether T is compatible with an STL-like iterable container.

- struct qpp::is\_iterable < T, to\_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), decltype(\*(std::declval < T >().end(
- struct qpp::is\_matrix\_expression< Derived >

Checks whether the type is an Eigen matrix expression.

struct qpp::is\_complex< T >

Checks whether the type is a complex type.

struct qpp::is\_complex< std::complex< T >>

Checks whether the type is a complex number type, specialization for complex types.

#### **Namespaces**

• qpp

Quantum++ main namespace.

## **Typedefs**

```
    template < typename... Ts>
        using qpp::to_void = typename make_void < Ts... > ::type
        Alias template that implements the proposal for void_t.
```


## 8.28.1 Detailed Description

Type traits.

# 8.29 types.h File Reference

Type aliases.

This graph shows which files directly or indirectly include this file:



## **Namespaces**

• qpp

Quantum++ main namespace.

## **Typedefs**

• using qpp::idx = std::size t

Non-negative integer index, make sure you use an unsigned type.

- using qpp::bigint = long long int
  - Big integer.
- using qpp::cplx = std::complex < double >

Complex number in double precision.

using qpp::ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector.

• using <a href="mailto:qpp::bra">qpp::bra</a> = Eigen::RowVectorXcd

Complex (double precision) dynamic Eigen row vector.

• using qpp::cmat = Eigen::MatrixXcd

Complex (double precision) dynamic Eigen matrix.

using qpp::dmat = Eigen::MatrixXd

Real (double precision) dynamic Eigen matrix.

template<typename Scalar >

```
using \ \ qpp::dyn\_mat = Eigen::Matrix < Scalar, \ Eigen::Dynamic, \ Eigen::Dynamic > \\
```

Dynamic Eigen matrix over the field specified by Scalar.

• template<typename Scalar >

```
using qpp::dyn_col_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 >
```

Dynamic Eigen column vector over the field specified by Scalar.

 $\bullet \ \ \text{template}{<} \text{typename Scalar} >$ 

```
using qpp::dyn_row_vect = Eigen::Matrix< Scalar, 1, Eigen::Dynamic >
```

Dynamic Eigen row vector over the field specified by Scalar.

8.29.1	Detailed	Descri	ntion
0.20.1	Detailed	DCGCII	DUVII

Type aliases.

8.30 /Users/vlad/qpp/README.md File Reference

# Index

ALL ALL AND	
/Users/vlad/qpp/README.md, 391	avg
~Codes	qpp, 36
qpp::Codes, 136	
$\sim$ Dynamic_bitset	b00
qpp::Dynamic_bitset, 158	qpp::States, 330
~Gates	b01
qpp::Gates, 174	qpp::States, 331
~IDisplay	b10
qpp::IDisplay, 190	qpp::States, 331
~IJSON	b11
	qpp::States, 331
qpp::IJSON, 192	
~Init	begin
qpp::Init, 195	qpp::QCircuit, 273, 274
$\sim$ NoiseBase	bigint
qpp::NoiseBase, 242	qpp, <mark>26</mark>
~QCircuit	Bit_circuit
qpp::QCircuit, 273	qpp::Bit_circuit, 131
~QEngine	bloch2rho
qpp::QEngine, 296	qpp, <mark>36</mark>
~RandomDevices	bra
	qpp, 26
qpp::RandomDevices, 318	qpp, 20
~Singleton	c reg
qpp::internal::Singleton, 322	c_reg_
~States	qpp::QCircuit::MeasureStep, 236
qpp::States, 328	cCTRL_custom
$\sim$ Timer	qpp::QCircuit, 276
qpp::Timer, 339	cCTRL
	qpp::QCircuit, 274–276
A_	CNOTba
qpp::internal::IOManipEigen, 199	qpp::Gates, 183
absm	CNOT
qpp, 28	qpp::Bit_circuit, 131
abssq	qpp::Bit_circuit::Gate_count, 170
	qpp::Gates, 183
qpp, 29	
adjoint	CTRL_custom
qpp, 30	qpp::QCircuit, 279
all	CTRL
qpp::Dynamic_bitset, 158	qpp::Gates, 175
anticomm	qpp::QCircuit, 277, 278
qpp, 30	cbegin
any	qpp::QCircuit, 274
gpp::Dynamic bitset, 158	cend
apply	qpp::QCircuit, 276
qpp, 31–33	check_cvector
applyCTRL	qpp::internal, 120
qpp, 33, 34	check_dims
applyQFT	qpp::internal, 120
qpp, 35	check_dims_match_cvect
applyTFQ	qpp::internal, 120
app. 35	check dims match mat

qpp::internal, 121	compperm
check_dims_match_rvect	qpp, 38
qpp::internal, 121	compute_probs_
check_eq_dims	qpp::NoiseBase, 242
qpp::internal, 121	compute_state_
check_matching_sizes	qpp::NoiseBase, 242
qpp::internal, 121	concurrence
check_no_duplicates	qpp, 40
qpp::internal, 121	conjugate
check_nonzero_size	qpp, 40
qpp::internal, 121	const_iterator
check_perm	qpp::QCircuit, 271 constants.h, 365
qpp::internal, 122	contfrac2x
check_qubit_cvector	
qpp::internal, 122	qpp, 40 convergents
check_qubit_matrix	qpp, 41
qpp::internal, 122	cor
check_qubit_rvector	qpp, 42
qpp::internal, 122	cosm
check_qubit_vector	qpp, 42
qpp::internal, 122	count
check_rvector	qpp::Dynamic_bitset, 158
qpp::internal, 122	count
check_square_mat	qpp::QCircuit, 292
qpp::internal, 123	COV
check_subsys_match_dims	qpp, 43
qpp::internal, 123	cplx
check_vector	qpp, 27
qpp::internal, 123 choi2kraus	ctrl
	qpp::QCircuit::GateStep, 187
qpp, 36	CustomException
choi2super	qpp::exception::CustomException, 138
qpp, 37	cwise
chop qpp, 116	qpp, 43
chop_	CZ
qpp::internal::IOManipEigen, 199	qpp::Gates, 183
classes/circuits.h, 355	
classes/codes.h, 356	d_
classes/exception.h, 357	qpp::NoiseBase, 245
classes/gates.h, 359	qpp::QCircuit, 292
classes/idisplay.h, 360	data
classes/init.h, 360	qpp::Dynamic_bitset, 158
classes/noise.h, 361	depth_
classes/random_devices.h, 362	qpp::QCircuit, 292 det
classes/reversible.h, 363	
classes/states.h, 363	qpp, 44
classes/timer.h, 364	difference_type qpp::QCircuit::iterator, 213
cmat	dirsum
qpp, 26	qpp, 44–46
Codes	dirsum2
qpp::Codes, 136	qpp::internal, 123
codeword	dirsumpow
qpp::Codes, 136	qpp, 46
comm	disp
qpp, 37	qpp, 47, 48
complement	display
qpp, 38	qpp::Dynamic_bitset, 159
-II-I- ; <del></del>	

qpp::IDisplay, 190	qpp::exception::InvalidIterator, 197
qpp::QCircuit, 279	qpp::exception::MatrixMismatchSubsys, 219
qpp::QCircuit::iterator::value_type_, 350	qpp::exception::MatrixNotCvector, 221
qpp::QEngine, 297	qpp::exception::MatrixNotRvector, 223
qpp::Timer, 339	qpp::exception::MatrixNotSquare, 225
qpp::internal::IOManipEigen, 199	qpp::exception::MatrixNotSquareNorCvector, 227
qpp::internal::IOManipPointer, 201	qpp::exception::MatrixNotSquareNorRvector, 229
qpp::internal::IOManipRange, 205	qpp::exception::MatrixNotSquareNorVector, 231
display_impl_	qpp::exception::MatrixNotVector, 233
qpp::internal::Display_Impl_, 152	qpp::exception::NoCodeword, 238
dits_	qpp::exception::NotBipartite, 248
qpp::QEngine, 302	qpp::exception::NotImplemented, 250
dmat	qpp::exception::NotQubitCvector, 252
qpp, 27	qpp::exception::NotQubitMatrix, 254
dyn_col_vect	qpp::exception::NotQubitRvector, 256
qpp, 27	qpp::exception::NotQubitSubsys, 258
dyn_mat	qpp::exception::NotQubitVector, 260
qpp, 27	qpp::exception::OutOfRange, 262
dyn_row_vect	qpp::exception::PermInvalid, 264
qpp, 27	qpp::exception::PermMismatchDims, 266
Dynamic_bitset	qpp::exception::QuditAlreadyMeasured, 313
qpp::Bit_circuit, 132	qpp::exception::SizeMismatch, 324
qpp::Dynamic_bitset, 157	qpp::exception::SubsysMismatchDims, 336
	qpp::exception::TypeMismatch, 343
ee	qpp::exception::UndefinedType, 345
qpp, 116	qpp::exception::Unknown, 347
egcd	qpp::exception::ZeroSize, 353
qpp, 49	execute
eig	qpp::QEngine, 297
qpp, 49	expandout
elem_	qpp::Gates, 175, 176
qpp::QCircuit::iterator, 217	experimental/experimental.h, 369
end	expm
qpp::QCircuit, 279, 280	qpp, <u>52</u>
end_	
qpp::Timer, 341	FRED
qpp::internal::IOManipPointer, 202	qpp::Bit_circuit, 132
qpp::internal::IOManipRange, 205	qpp::Bit_circuit::Gate_count, 171
entanglement	qpp::Gates, 183
qpp, <del>5</del> 0	factors
entanglement.h, 366	qpp, 53
entropies.h, 368	Fd
entropy	qpp::Gates, 177
qpp, <del>5</del> 1	fill_Ks_
eps	qpp::QuditDepolarizingNoise, 316
qpp, 116	fill_probs_
evals	qpp::QuditDepolarizingNoise, 316
qpp, <del>5</del> 1	first_
evects	qpp::internal::IOManipRange, 206
qpp, 52	flip
Exception	qpp::Dynamic_bitset, 159
qpp::exception::DimsInvalid, 141	functions.h, 369
qpp::exception::DimsMismatchCvector, 143	funm
qpp::exception::DimsMismatchMatrix, 145	qpp, 53
qpp::exception::DimsMismatchRvector, 147	
qpp::exception::DimsMismatchVector, 149	GHZ
qpp::exception::DimsNotEqual, 151	qpp::States, 331
qpp::exception::Duplicates, 154	gate
qpp::exception::Exception, 169	qpp::QCircuit, 280, 281

gate	qpp::QCircuit, 284, 285
qpp::QCircuit::GateStep, 187	qpp::QEngine, 298, 299
gate_count	get_measurement_count
qpp::Bit_circuit, 134	qpp::QCircuit, 285
gate_custom	get_measurements_
qpp::QCircuit, 281	qpp::QCircuit, 286
gate_fan	get_name
qpp::QCircuit, 282, 283	qpp::Gates, 178
gate_type_	qpp::QCircuit, 286
qpp::QCircuit::GateStep, 187	get_nc
GateStep	qpp::QCircuit, 286
gpp::QCircuit::GateStep, 186	get_non_measured
GateType	qpp::QCircuit, 286
qpp::QCircuit, 271	get_not_measured
_ " '	qpp::QEngine, 299
Gates	
qpp::Gates, 174	get_nq
gates_	qpp::QCircuit, 287
qpp::QCircuit, 292	get_num_subsys
gates_ip_	qpp::internal, 123
qpp::QCircuit::iterator::value_type_, 350	get_prng
gcd	qpp::RandomDevices, 319
qpp, 54	get_probs
gconcurrence	qpp::NoiseBase, 244
qpp, 54	qpp::QEngine, 299
•••	get_psi
generated_	qpp::QEngine, 299
qpp::NoiseBase, 245	get_ref_psi
get	
qpp::Dynamic_bitset, 160	qpp::QEngine, 300
get_Ks	get_relative_pos_
qpp::NoiseBase, 243	qpp::QEngine, 300
get_circuit	get_step_count
qpp::QEngine, 298	qpp::QCircuit, 287
get d	get_thread_local_instance
qpp::NoiseBase, 243	qpp::internal::Singleton, 322
qpp::QCircuit, 283	grams
	qpp, 55, 56
get_dim_subsys	
qpp::internal, 123	Н
get_dit	qpp::Gates, 183
qpp::QEngine, 298	heig
get_dits	qpp, 56
qpp::QEngine, 298	hevals
get duration	
qpp::Timer, 340	qpp, 57
get_gate_count	hevects
qpp::QCircuit, 283	qpp, 57
get_gate_depth	i_
qpp::QCircuit, 284	qpp::NoiseBase, 245
get_gates_	IDisplay
qpp::QCircuit, 284	qpp::IDisplay, 189
get_instance	IJSON
qpp::internal::Singleton, 322	qpp::IJSON, 192
get_last_idx	IOManipEigen
qpp::NoiseBase, 243	qpp::internal::IOManipEigen, 199
get_last_K	IOManipPointer
qpp::NoiseBase, 244	qpp::internal::IOManipPointer, 201
get_last_p	IOManipRange
qpp::NoiseBase, 244	qpp::internal::IOManipRange, 204, 205
get_measured	ld

qpp::Gates, 178	qpp::NoiseBase, 246
ld2	· ·
qpp::Gates, 184 idx	last_ qpp::internal::IOManipRange, 206
qpp, 28	lcm
idx_infty	qpp, 63
qpp, 116	load
index_	qpp, 64
qpp::Dynamic_bitset, 160	qpp::RandomDevices, 319
infty	loadMATLAB
qpp, 116	qpp, 64, 65
Init	logdet
qpp::Init, 195	qpp, 66
input_output.h, 374	logm
instruments.h, 375	qpp, 66
internal/classes/iomanip.h, 376	lognegativity qpp, 67
internal/classes/singleton.h, 377	<b>άρρ, 67</b>
internal/util.h, 378	MATLAB/matlab.h, 380
internal::Singleton < const Codes >	MODMUL
qpp::Codes, 137 internal::Singleton< const Gates >	qpp::Gates, 178
qpp::Gates, 183	marginalX
internal::Singleton< const Init >	qpp, 67
qpp::Init, 195	marginalY
internal::Singleton< const States >	qpp, 69
qpp::States, 330	mats_
internal::Singleton< RandomDevices >	qpp::QCircuit::MeasureStep, 236
qpp::RandomDevices, 320	maxn
inverse	qpp, 116
qpp, 57	measure
invperm	qpp, 69–74
qpp, 58	measure_seq
ip	qpp, 74, 75
qpp, 58, 59	MeasureStep
ip_	qpp::QCircuit::MeasureStep, 235
<pre>qpp::QCircuit::iterator::value_type_, 350</pre>	MeasureType
isprime	qpp::QCircuit, 272
qpp, <del>5</del> 9	measured_
iterator	qpp::QCircuit, 292
qpp::QCircuit::iterator, 214	measurement_count_ qpp::QCircuit, 292
iterator_category	measurement_type_
qpp::QCircuit::iterator, 213	qpp::QCircuit::MeasureStep, 236
jn	measurements
qpp::States, 328	qpp::QCircuit, 293
4ppotatoo, 020	measurements_ip_
ket	<pre>qpp::QCircuit::iterator::value_type_, 351</pre>
qpp, 28	measureV
kraus2choi	qpp::QCircuit, 287, 288
qpp, 59	measureZ
kraus2super	qpp::QCircuit, 288
qpp, 60	mes
kron	qpp::States, 328
qpp, 60–62	minus
kron2	qpp::States, 329
qpp::internal, 124	mket
kronpow	qpp, 75, 76
qpp, 62	modinv
Ks_	qpp, 76

modmul	qpp::NoiseBase, 244, 245
qpp, 77	operator++
modpow	qpp::QCircuit::iterator, 215
qpp, 77	operator-
mprj	qpp::Dynamic_bitset, 161
qpp, 78	operator=
msg_	qpp::IDisplay, 190
qpp::exception::Exception, 170	qpp::IJSON, 192, 193
multiidx2n	qpp::QCircuit::iterator, 215
qpp, 79	qpp::QCircuit::iterator::value_type_, 350
qpp::internal, 124	qpp::Timer, 340
	qpp::internal::IOManipPointer, 202
n2multiidx	qpp::internal::IOManipRange, 205
qpp, 79	qpp::internal::Singleton, 322
qpp::internal, 124	operator==
N_	qpp::Dynamic_bitset, 162
qpp::Dynamic_bitset, 165	qpp::QCircuit::iterator, 216
qpp::internal::IOManipPointer, 202	operator"" _bra
NOT	qpp::literals, 125
qpp::Bit_circuit, 132	operator""_i
qpp::Bit_circuit::Gate_count, 171	qpp, 82
name	
qpp::QCircuit, 293	qpp::literals, 125
qpp::QCircuit::GateStep, 187	operator"" _ket
qpp::QCircuit::MeasureStep, 236	qpp::literals, 126
	operator""_prj
nc_	qpp::literals, 126
qpp::QCircuit, 293	0
negativity	p_ qpp::internal::IOManipPointer, 202
qpp, 80	
noise_type	pGHZ
qpp::NoiseBase, 241	qpp::States, 332
NoiseBase	pb00
qpp::NoiseBase, 241	qpp::States, 331
none	pb01
qpp::Dynamic_bitset, 160	qpp::States, 331
norm	pb10
qpp, 81	qpp::States, 332
normalize	pb11
qpp, 81	qpp::States, 332
nq_	pi
qpp::QCircuit, 293	qpp, 117
number_theory.h, 380	plus
_ ,	qpp::States, 329
offset_	pointer
qpp::Dynamic_bitset, 161	qpp::QCircuit::iterator, 213
omega	powm
qpp, 82	qpp, 82
one	prj
qpp::States, 329	qpp, 83
operations.h, 382	prng_
operator!=	qpp::RandomDevices, 320
qpp::Dynamic_bitset, 161	probs_
qpp::QCircuit::iterator, 214	
	qpp::NoiseBase, 246
operator<<	qpp::QEngine, 302
qpp::IDisplay, 191	prod
qpp::QCircuit, 290, 291	qpp, 83, 84
operator*	psi_
qpp::QCircuit::iterator, 215	qpp::QEngine, 302
operator()	ptrace

qpp, 84, 85	contfrac2x, 40
ptrace1	convergents, 41
qpp, 85, 86	cor, 42
ptrace2	cosm, 42
qpp, 86, 87	cov, <del>43</del>
ptranspose	cplx, 27
qpp, 87, 88	cwise, 43
pW	det, 44
qpp::States, 332	dirsum, 44–46
px0	dirsumpow, 46
qpp::States, 332	disp, 47, 48
px1	dmat, 27
qpp::States, 332	dyn_col_vect, 27
py0 qpp::States, 333	dyn_mat, 27
py1	dyn_row_vect, 27
qpp::States, 333	ee, 116
pz0	egcd, 49
gpp::States, 333	eig, 49
pz1	entanglement, 50
qpp::States, 333	entropy, 51
qppetatos, ooc	eps, 116
QCircuit	evals, 51 evects, 52
qpp::QCircuit, 273	,
QEngine	expm, 52
qpp::QCircuit, 291	factors, 53 funm, 53
qpp::QEngine, 296	gcd, 54
QFT	gconcurrence, 54
qpp, 88	grams, 55, 56
qpp::QCircuit, 288	heig, 56
QPP_UNUSED_	hevals, 57
qpp.h, 386	hevects, 57
qcd_	idx, 28
qpp::QCircuit::iterator, 217	idx_infty, 116
qpp::QEngine, 302	infty, 116
qmutualinfo	inverse, 57
qpp, 89	invperm, 58
qpp, 13	ip, 58, 59
absm, 28 abssq, 29	isprime, 59
adjoint, 30	ket, 28
anticomm, 30	kraus2choi, 59
apply, 31–33	kraus2super, 60
applyCTRL, 33, 34	kron, 60–62
applyQFT, 35	kronpow, 62
applyTFQ, 35	lcm, 63
avg, 36	load, 64
bigint, 26	loadMATLAB, 64, 65
bloch2rho, 36	logdet, 66
bra, 26	logm, 66
choi2kraus, 36	lognegativity, 67
choi2super, 37	marginalX, 67
chop, 116	marginalY, 69
cmat, 26	maxn, 116
comm, 37	measure, 69-74
complement, 38	measure_seq, 74, 75
compperm, 38	mket, 75, 76
concurrence, 40	modinv, 76
conjugate, 40	modmul, 77

modpow, 77	uniform, 114
mprj, 78	var, 115
multiidx2n, 79	x2contfrac, 115
n2multiidx, 79	qpp.h, 384
negativity, 80	QPP_UNUSED_, 386
norm, 81	qpp::Bit_circuit, 129
normalize, 81 omega, 82	Bit_circuit, 131 CNOT, 131
operator"" _i, 82	Dynamic_bitset, 132
pi, 117	FRED, 132
powm, 82	gate_count, 134
prj, 83	NOT, 132
prod, 83, 84	reset, 132
ptrace, 84, 85	SWAP, 133
ptrace1, 85, 86	TOF, 133
ptrace2, 86, 87	X, 133
ptranspose, 87, 88	qpp::Bit_circuit::Gate_count, 170
QFT, 88	CNOT, 170
qmutualinfo, 89	FRED, 171
rand, 90-92	NOT, 171
randH, 92	SWAP, 171
randidx, 93	TOF, 171
randket, 93	X, 171
randkraus, 93	qpp::Codes, 134
randn, 94, 95	∼Codes, 136
randperm, 96	Codes, 136
randprime, 96	codeword, 136
randprob, 97	internal::Singleton< const Codes >, 137
randrho, 97	Type, 135
randU, 97	qpp::Dynamic_bitset, 155
randV, 98	~Dynamic_bitset, 158
renyi, 98, 99	all, 158
reshape, 99	any, 158
rho2bloch, 100	count, 158
rho2pure, 100 save, 101	data, 158 display, 159
saveMATLAB, 101, 102	Dynamic_bitset, 157
schatten, 102	flip, 159
schmidtA, 103	get, 160
schmidtB, 103, 104	index_, 160
schmidtcoeffs, 104, 105	N_, 165
schmidtprobs, 105, 106	none, 160
sigma, 106	offset_, 161
sinm, 107	operator!=, 161
spectralpowm, 107	operator-, 161
sqrtm, 108	operator==, 162
sum, 108, 109	rand, 162, 163
super2choi, 109	reset, 163
svals, 110	set, 163, 164
svd, 110	size, 164
svdU, 110	storage_size, 164
svdV, 111	storage_size_, 165
syspermute, 111, 112	storage_type, 157
TFQ, 112	to_string, 164
to_void, 28	v_, 165
trace, 112	value_type, 157
transpose, 113	qpp::Gates, 172
tsallis, 113, 114	∼Gates, 174

CNOTba, 183 CNOT, 183 CTRL, 175 CZ, 183 expandout, 175, 176 FRED, 183 Fd, 177 Gates, 174 get_name, 178 H, 183 Id, 178 Id, 178 Id, 178 Id, 178 RN, 179 RX, 179 RX, 179 RX, 179 RX, 180 RZ, 180 SWAPd, 180 SWAPd, 180 SWAP, 184 TOF, 184 X, 184 Xd, 182 Y, 185 Zd, 182 Zd, 182 Zd, 182 Zd, 182 Cpp://loise/lase All 188 Compute_probs_yell Significant = Signi	ONOT. 100	N. D. G.
CTRL, 175 CZ, 183 expandout, 175, 176 FRED, 183 Fd, 177 Gates, 174 get_name, 178 H, 183 Id, 178 Id2, 184 internal::Singleton< const Gates >, 183 MODMUL, 178 RN, 179 RY, 180 RZ, 180 SWAP, 180 TOF, 184 X, 184 Xd, 182 Y, 185 Z, 186 Z, 187 Z, 188 Z, 189 Z, 289 Z, 2		
CZ, 183 expandout, 175, 176 FRED, 183 expandout, 175, 176 FRED, 183 Fd, 177 Gates, 174 get_name, 178 H, 183 Id, 178 Id2, 184 internal:Singleton< const Gates >, 183 MODMUL, 178 Rn, 179 RX, 179 RY, 180 RZ, 180 SWAPd, 180 SWAPd, 180 SWAPd, 180 SWAP, 184 TOF, 184 Xd, 182 Y, 185 Zd, 182 Zd, 182 Zqp::Display, 188 ~Ibisplay, 180 Operator=, 190 qibisplay, 190 display, 190 liDisplay, 190 display, 190 porator=, 190 qpp::USON, 192 operator=, 190 qpp::USON, 192 operator=, 190 qpp::USON, 193 qpp::Init:nail::Singleton< const Init >, 195 qpp::NoiseBase ~NoiseBase, 242 compute probs_, 242 question and the probs probs, 244 question and the probable and the probable and probable	•	•
expandout, 175, 176 FRED, 183 Fd, 177 Gates, 174 get_name, 178 H, 183 Id, 178 H, 183 Id, 178 Id, 179 RX, 179 RX, 179 RX, 180 RZ, 180 SWAP, 180 SWAP, 184 TOF, 184 X, 184 X, 184 X, 184 X, 184 X, 184 X, 185 Z,		• —
FRED, 183 Fd, 177 Gates, 174 get_name, 178 H, 183 Id, 178 Id2, 184 Internal:Singleton< const Gates >, 183 MODMUL, 178 Rn, 179 RY, 180 RZ, 180 SWAPC, 184 SWAPC, 184 TOF, 184 X, 184 Xd, 182 Y, 185 Z, 185 Qap::Display, 180 Operator<, 191 operator<, 191 operator<, 190 operator<, 192, 193 to JSON, 193 operator<, 280 operator<, 290		
Fd, 177 Gates, 174 get_name, 178 H, 183 Id, 178 Id, 179 RN, 179 RN, 179 RY, 180 RZ, 180 SWAP, 180 SWAP, 184 T, 184 TOF, 184 X, 184 Xd, 182 Y, 185 Z, 189 Qpp:://lisplay, 188 ~/loisplay, 190 Gisplay,	•	
Gates, 174 get_name, 178 H, 183 Id, 178 Id, 178 Id, 178 Id, 184 Id2, 184 Internal::Singleton< const Gates >, 183 MODMUL, 179 RN, 179 RN, 179 RX, 179 RY, 180 S, 184 SWAPd, 180 S, 184 SWAPd, 180 S, 184 TOF, 184 Xd, 182 TOF, 185 Z,		<pre>qpp::NoiseType::StateDependent, 325</pre>
get_name, 178 H, 183 H, 183 Begin, 273, 274 cCTRL, 274-276 cTRL, 274-276 CTRL, 274-276 CTRL, 277, 278 chair, 179 Crail, 277, 278 chegin, 274 cend, 276 const_iterator, 271 count, 292 S, 184 SWAPd, 180 SWAP, 180 SWAP, 184 T, 184 TOF, 184 TOF, 184 TOF, 184 X, 184 TOF, 184 X, 184 TOF, 184 X, 185 Z, 185 Zd, 182 qpp:://display, 189 operator <, 191 operator <, 191 operator <, 190 qpp:://display, 189 qpp:://display, 190 qpp:://display, 189 qpt_measurements_, 286 qpt_na, 287 qpt_na, 287 qpt_na, 287 db,	Fd, 177	<pre>qpp::NoiseType::StateIndependent, 325</pre>
ii, 183 iid, 178 iid, 184 internal::Singleton< const Gates >, 183 MODMUL, 178 Rn, 179 RN, 179 RN, 179 RY, 180 SUAPH, 180 SUAPH, 181 SUBPLANT SUBPL	Gates, 174	qpp::QCircuit, 267
Id., 178	get_name, 178	$\sim$ QCircuit, 273
Id., 178	H, 183	begin, 273, 274
Id2, 184		cCTRL custom, 276
internal::Singleton < const Gates > , 183  MODMUL, 178  Rn, 179  Rx, 179  RX, 179  RX, 179  RY, 180  S, 184  SWAPd, 180  SWAPd, 180  SWAP, 184  TOF, 184  X, 184  X, 184  X, 182  Y, 185  Z, 185  Z, 185  Z, 185  Z, 185  Z, 185  Z, 185  Qpp::IDisplay, 188  ~IDisplay, 188  ~IDisplay, 190  display, 190  Qpp::IJSON, 191  ~USON, 192  Qpp::IJSON, 192  Qpp::IJSON, 192  Qpp::IJSON, 193  qpp::Init, 195  Init, 195  Init near-  And		
MODMUL, 178 Rn, 179 Rx, 179 Rx, 179 Ry, 180 Ry, 180 Ry, 180 SWAPd, 180 SWAPd, 180 SWAPd, 180 SWAP, 184 T, 184 T, 184 TOF, 184 SWA, 182 SWAPd, 182 SWAPd, 185 SWAP, 185 SWAP, 186 SWAP, 187 SWAP, 188 TOF, 188 SWAP, 189 SWAP, 184 SWAP, 184 SWAP, 184 SWAP, 184 SWAP, 180 SWAP, 184 SWAP, 184 SWAP, 184 SWAP, 184 SWAP, 280 SWAP, 184 SWAP, 184 SWAP, 292 SWAP, 280 SWAP, 184 SWAP, 280 SWAP, 184 SWAP, 280 SWAP, 184 SWAP, 280		•
Rn, 179 RX, 179 RX, 180 Const_iterator, 271 RZ, 180 S, 184 SWAPd, 180 SWAP, 184 TOF, 184 X, 184 Ad, 182 Y, 185 Z, 185 Zd, 182 Spel_d, 283 Spel_d, 283 Spel_depth, 284 Spel_depth, 286 Spel_dep		
RX, 179 RY, 180 RY, 180 Const_iterator, 271 Count 292 S, 184 SWAPd, 180 SWAPd, 180 SWAP, 184 T, 184 COUNT 292 SWAP, 184 TOF, 184 SWAP, 184 SWAP, 185 SQAP, 185 SQAP, 185 SQAP, 185 SQAP, 185 SQAP, 186 SQAP, 189 SQAP, 289 SQAP, 289 SQAP, 189 SQAP, 289 SQAP, 28 SQAP, 289 SQAP, 289 SQAP, 289 SQAP, 289 SQAP, 289 SQAP, 289 SQAP		
RY, 180		-
RZ, 180 S, 184 SWAPd, 180 SWAP, 184 Coun_, 292 SWAP, 184 Coun_, 293 Coun_, 292 SWAP, 184 Coun_, 293 Coun_, 294 Coun_, 294 Coun_, 294 Coun_, 293 Coun_, 293 Coun_, 293 Coun_, 293 Coun_, 293 Coun_, 293 Coun_, 294 Coun_, 293 Coun_, 293 Coun_, 293 Coun_, 293 Coun_, 294 Coun_, 294 Coun_, 294 Coun_, 294 Coun_, 294 Coun_, 295 Coun_, 296 Coun_, 296 Coun_, 296 Coun_, 296 Coun_, 297 Cou		•
S, 184 SWAPd, 180 SWAP, 184 T, 184 TOF, 184 SWAP, 184 TOF, 184 SWAP, 185 TOF, 184 SWAP, 185 SWAP, 185 SWAP, 185 SWAP, 185 SWAP, 186 SWAP, 186 SWAP, 187 SWAP, 188 SWAP, 189 SWAP, 189 SWAP, 189 SWAP, 189 SWAP, 180 SWAP, 184 SWAP, 280 SWAP, 184 SWAP, 184 SWAP, 184 SWAP, 184 SWAP, 184 SWAP, 280 SWAP, 184 SWAP, 184 SWAP, 280 SWAP, 184 SWAP, 184 SWAP, 280 SWAP, 184 SWAP, 184 SWAP, 280 SWAP, 184 SWAP, 184 SWAP, 280 SWAP, 184 SWAP, 18 SWAP, 18 SWAP,		
SWAPd, 180 SWAP, 184 T, 184 T, 184 SWAP, 184 TOF, 184 SWAP, 185 SWAP, 186 SWAP, 186 SWAP, 186 SWAP, 186 SWAP, 187 SWAP, 1884 SAP, 1884 SAP, 1884 SAP, 1884 SAP, 1885 SARP SAP, 188 SAPP SAPP SAPP SAPP SAPP SAPP SAPP SAPP		
SWAP, 184 T, 184 TOF, 184 TOF, 184 X, 184 X, 182 X, 185 Z, 185 Z, 185 Zd, 182 qpp:://Display, 190 display, 190 display, 190 display, 190 display, 189 operator<, 191 operator=, 190 qpp:://SON, 192 operator=, 192, 193 to_JSON, 192 dipp:://son, 195 lnit, 195 lnit, 195 lnit, 195 lnit, 195 lorse lo	•	
T, 184 TOF, 184 TOF, 184 X, 184 X, 184 X, 182 Xd, 182 Y, 185 GateType, 271 Zd, 185 Zd, 182 qpp::IDisplay, 188	•	• —
TOF, 184     X, 184     Xd, 182     Y, 185     GateType, 271     Zd, 185     Zd, 182     Qpp::IDisplay, 180     ~ IDisplay, 190     idisplay, 190     idisplay, 190     idisplay, 189     operator=, 190     qpp::JSON, 191     ~ IJSON, 192     idisploy, 193     qpp::Init, 193     ~ Init, 195     init renal::Singleton < const Init >, 195     qpp::NoiseBase     ~ NoiseBase, 242     compute_probs_, 242     compute_state_, 245     get_last_idx, 243     get_last_idx, 243     get_last_idx, 243     get_last_idx, 244     get_last_p, 244     get_proc, 288     qpp::Qcircuit::Gate Step, 185     Ks_, 246     qpp::Qcircuit::Gate Step, 185     Ks_, 246     qpp::Qcircuit::Gate Step, 185	,	
X, 184 Xd, 182 Xd, 182 Y, 185 Z, 185 Z, 185 Zd, 182 qpp::IDisplay, 188		
Xd, 182 Y, 185 Z, 185 Zd, 182 qpp::IDisplay, 188		
Y, 185 Z, 185 Zd, 182 gp::IDisplay, 188		gate_custom, 281
Z, 185 Zd, 182 Zd, 182  qpp::IDisplay, 188	Xd, 182	gate_fan, 282, 283
Zd, 182  qpp::IDisplay, 188	Y, 185	GateType, 271
qpp::IDisplay, 188	Z, 185	gates_, 292
~IDisplay, 190         get_gate_depth, 284           display, 190         get_gates_, 284           IDisplay, 189         get_measured, 284, 285           operator         get_measurement_count, 285           operator=, 190         get_measurements_, 286           qpp::IJSON, 191         get_neasurements_, 286           vIJSON, 192         get_nc, 286           operator=, 192, 193         get_nc, 287           to_JSON, 193         get_nc, 287           dp:_Init, 193         MeasureType, 272           ~Init, 195         measurement_count_, 292           internal::Singleton         const Init >, 195           dpp::NoiseBase         measurement_count_, 292           measureV, 287, 288         measureZ, 288           compute_probs_, 242         name_, 293           compute_state_, 242         nc_, 293           d_, 245         operator<<<, 290, 291	Zd, 182	get_d, 283
display, 190 IDisplay, 189     operator<<, 191     operator<<, 191     operator=, 190  qet_measurement_count, 285     operator=, 190  qpp::IJSON, 191     operator=, 192, 193     to_JSON, 192     IJSON, 193  qpp::Init, 195     internal::Singleton< const Init >, 195  qpp::NoiseBase     ~NoiseBase, 242     compute_probs_, 242     compute_state_, 242     d_, 245     get_dse_, 244     get_dse_, 245     get_measurement_count_, 292     measurement_count_, 293     measurev, 288     measureV, 287, 288     measureV, 287, 288     measureZ, 288     compute_probs_, 242     compute_state_, 242     d_, 245     get_d, 243     get_d, 243     get_last_idx, 243     get_last_idx, 244     get_last_dx, 244     get_last_dx, 244     get_last_p, 244     get_last_p, 244     get_probs_, 244     i_, 245     ks_, 246     qpp::QCircuit::GateStep, 185	qpp::IDisplay, 188	get_gate_count, 283
display, 190       get_gates_, 284         IDisplay, 189       get_measured, 284, 285         operator<<, 191	∼IDisplay, 190	
IDisplay, 189		
operator < < , 191	• •	
operator=, 190  qpp::IJSON, 191	• • •	<del>-</del> —
qpp::IJSON, 191	•	<del>-</del>
~IJSON, 192       get_nc, 286         JSON, 192       get_non_measured, 286         operator=, 192, 193       get_nq, 287         to_JSON, 193       get_step_count, 287         qpp::Init, 193       MeasureType, 272         ~Init, 195       measured_, 292         Init, 195       measurement_count_, 292         internal::Singleton< const Init >, 195       measurements_, 293         qpp::NoiseBase       measureZ, 288         ~NoiseBase, 242       measureZ, 288         compute_probs_, 242       name_, 293         compute_state_, 242       nc_, 293         d_, 245       operator<<<, 290, 291	•	
IJSON, 192		
operator=, 192, 193 to_JSON, 193		
to_JSON, 193  qpp::Init, 193		
qpp::Init, 193       MeasureType, 272         ~Init, 195       measured_, 292         Init, 195       measurement_count_, 292         internal::Singleton < const Init >, 195       measurements_, 293         qpp::NoiseBase       measureV, 287, 288         ~NoiseBase, 242       measureZ, 288         compute_probs_, 242       name_, 293         compute_state_, 242       nc_, 293         d_, 245       nq_, 293         generated_, 245       operator <<<, 290, 291	•	
~Init, 195 Init, 195 Init, 195 Internal::Singleton< const Init >, 195  qpp::NoiseBase	<del>-</del>	
Init, 195 internal::Singleton < const Init >, 195  qpp::NoiseBase		
internal::Singleton < const Init >, 195  qpp::NoiseBase	•	<del>_</del>
qpp::NoiseBase       measureV, 287, 288         ~NoiseBase, 242       measureZ, 288         compute_probs_, 242       name_, 293         compute_state_, 242       nc_, 293         d_, 245       nq_, 293         generated_, 245       operator <<<, 290, 291	,	
NoiseBase, 242 <pre>compute_probs_, 242 compute_state_, 242</pre> <pre>d_, 245</pre> generated_, 245 get_Ks, 243 get_d, 243 get_last_idx, 243 get_last_K, 244 get_probs, 244 i_, 245 measureZ, 288 name_, 293 nc_, 293 nq_, 293 operator <<, 290, 291 QCircuit, 273 QEngine, 291 QFT, 288 get_last_K, 244 step_types_, 293 get_last_p, 244 StepType, 272 get_probs, 244 i_, 245 Ks_, 246 measureZ, 288 name_, 293 nc_, 293 nc_, 293 perator <<, 290, 291 QFT, 288 step_types_, 291 TFQ, 289 to_JSON, 289 Ks_, 246 qpp::QCircuit::GateStep, 185		
compute_probs_, 242       name_, 293         compute_state_, 242       nc_, 293         d_, 245       nq_, 293         generated_, 245       operator <<, 290, 291		
compute_state_, 242       nc_, 293         d_, 245       nq_, 293         generated_, 245       operator <<, 290, 291		
d_, 245       nq_, 293         generated_, 245       operator <<, 290, 291	compute_probs_, 242	name_, 293
generated_, 245 get_Ks, 243 get_d, 243 get_last_idx, 243 get_last_K, 244 get_last_p, 244 get_probs, 244 i_, 245 Ks_, 246 get_ks, 245 get_last_c, 246 get_last_c, 246 get_last_c, 244 get_probs, 244 get_probs, 244 get_probs, 244 get_probs, 244 get_probs, 245 get_probs, 246 get_p	compute_state_, 242	nc_, 293
get_Ks, 243       QCircuit, 273         get_d, 243       QEngine, 291         get_last_idx, 243       QFT, 288         get_last_K, 244       step_types_, 293         get_last_p, 244       StepType, 272         get_probs, 244       TFQ, 289         i_, 245       to_JSON, 289         Ks_, 246       qpp::QCircuit::GateStep, 185	d_, 245	nq_, 293
get_d, 243       QEngine, 291         get_last_idx, 243       QFT, 288         get_last_K, 244       step_types_, 293         get_last_p, 244       StepType, 272         get_probs, 244       TFQ, 289         i_, 245       to_JSON, 289         Ks_, 246       qpp::QCircuit::GateStep, 185	generated_, 245	operator<<, 290, 291
get_last_idx, 243 get_last_K, 244 get_last_p, 244 get_probs, 244 i_, 245 Ks_, 246  QFT, 288 step_types_, 293 StepType, 272 TFQ, 289 to_JSON, 289 qpp::QCircuit::GateStep, 185	get_Ks, 243	QCircuit, 273
get_last_idx, 243 get_last_K, 244 get_last_p, 244 get_probs, 244 i_, 245 Ks_, 246  QFT, 288 step_types_, 293 StepType, 272 TFQ, 289 to_JSON, 289 qpp::QCircuit::GateStep, 185	get_d, 243	QEngine, 291
get_last_K, 244 step_types_, 293 get_last_p, 244 StepType, 272 get_probs, 244 TFQ, 289 i_, 245 to_JSON, 289 Ks_, 246 qpp::QCircuit::GateStep, 185	<del>-</del> -	_
get_last_p, 244 StepType, 272 get_probs, 244 TFQ, 289 i_, 245 to_JSON, 289 Ks_, 246 qpp::QCircuit::GateStep, 185	<del>-</del>	•
get_probs, 244  i_, 245  Ks_, 246  TFQ, 289  to_JSON, 289  qpp::QCircuit::GateStep, 185		
i_, 245 to_JSON, 289 Ks_, 246 qpp::QCircuit::GateStep, 185	·	
Ks_, 246 qpp::QCircuit::GateStep, 185		
110136_type, 241 CIII_, 107	<del></del> -	
	110136_type, 241	GIII_, 107

gate_, 187	subsys_, 302
gate_type_, 187	to_JSON, 301
GateStep, 186	qpp::QubitAmplitudeDampingNoise, 303
name_, 187	QubitAmplitudeDampingNoise, 304
target_, 187	qpp::QubitBitFlipNoise, 304
qpp::QCircuit::MeasureStep, 234	QubitBitFlipNoise, 305
c_reg_, 236	qpp::QubitBitPhaseFlipNoise, 306
mats_, 236	QubitBitPhaseFlipNoise, 307
MeasureStep, 235	qpp::QubitDepolarizingNoise, 307  QubitDepolarizingNoise, 308
measurement_type_, 236	•
name_, 236	qpp::QubitPhaseDampingNoise, 309 QubitPhaseDampingNoise, 310
target_, 236 qpp::QCircuit::iterator, 212	qpp::QubitPhaseFlipNoise, 310
difference_type, 213	QubitPhaseFlipNoise, 311
elem_, 217	qpp::QuditDepolarizingNoise, 314
iterator, 214	fill_Ks_, 316
iterator_category, 213	fill_probs_, 316
operator!=, 214	QuditDepolarizingNoise, 315
operator*, 215	qpp::RandomDevices, 317
operator++, 215	~RandomDevices, 318
operator=, 215	get prng, 319
operator==, 216	internal::Singleton< RandomDevices >, 320
pointer, 213	load, 319
qcd_, 217	prng_, 320
reference, 214	RandomDevices, 318
set_begin_, 216	rd_, 320
set_end_, 216	save, 319
value_type, 214	qpp::States, 325
qpp::QCircuit::iterator::value_type_, 348	~States, 328
display, 350	b00, 330
gates_ip_, 350	b01, 331
ip_, 350	b10, 331
measurements_ip_, 351	b11, 331
operator=, 350	GHZ, 331
type_, 351	internal::Singleton < const States >, 330
value type , 349	jn, 328
value_type_qcd_, 351	mes, 328
qpp::QEngine, 294	minus, 329
$\sim$ QEngine, 296	one, 329
display, 297	pGHZ, 332
dits_, 302	pb00, 331
execute, 297	pb01, 331
get_circuit, 298	pb10, 332
get_dit, 298	pb11, 332
get_dits, 298	plus, 329
get_measured, 298, 299	pW, 332
get_not_measured, 299	px0, 332
get_probs, 299	px1, 332
get_psi, 299	py0, 333
get_ref_psi, 300	py1, 333
get_relative_pos_, 300	pz0, 333
probs_, 302	pz1, 333
psi_, 302	States, 328
QEngine, 296	W, 333
qcd_, 302	x0, 333
reset, 300	x1, 334
set_dit, 300	y0, <del>334</del>
set_measured_, 301	y1, <del>334</del>

z0, 334	type_description, 224
z1, 334	qpp::exception::MatrixNotSquare, 224
zero, 330	Exception, 225
qpp::Timer	type_description, 226
$\sim$ Timer, 339	qpp::exception::MatrixNotSquareNorCvector, 226
display, 339	Exception, 227
end_, 341	type_description, 228
get_duration, 340	qpp::exception::MatrixNotSquareNorRvector, 228
operator=, 340	Exception, 229
start_, 341	type_description, 230
tic, 340	qpp::exception::MatrixNotSquareNorVector, 230
tics, 341	Exception, 231
Timer, 338, 339	type_description, 232
toc, 341	qpp::exception::MatrixNotVector, 232
qpp::Timer< T, CLOCK_T >, 337	Exception, 233
app::exception, 117	type_description, 234
app::exception::CustomException, 137	qpp::exception::NoCodeword, 237
CustomException, 138	Exception, 238
type_description, 139	type_description, 239
what_, 139	qpp::exception::NotBipartite, 247
qpp::exception::DimsInvalid, 140	Exception, 248
Exception, 141	type_description, 248
type_description, 141	qpp::exception::NotImplemented, 249
qpp::exception::DimsMismatchCvector, 142	Exception, 250
Exception, 143	type_description, 250
type_description, 143	qpp::exception::NotQubitCvector, 251
qpp::exception::DimsMismatchMatrix, 144	Exception, 252
Exception, 145	type_description, 252
type_description, 145	qpp::exception::NotQubitMatrix, 253
qpp::exception::DimsMismatchRvector, 146	Exception, 254
Exception, 147	type_description, 254
type_description, 147	qpp::exception::NotQubitRvector, 255
qpp::exception::DimsMismatchVector, 148	Exception, 256
Exception, 149	type_description, 256
type_description, 149	qpp::exception::NotQubitSubsys, 257
qpp::exception::DimsNotEqual, 150	Exception, 258
Exception, 151	type_description, 258
type description, 151	qpp::exception::NotQubitVector, 259
qpp::exception::Duplicates, 153	Exception, 260
Exception, 154	type_description, 260
type_description, 154	qpp::exception::OutOfRange, 261
qpp::exception::Exception, 166	Exception, 262
Exception, 169	type_description, 262
msg_, 170	qpp::exception::PermInvalid, 263
type_description, 169	Exception, 264
	•
what, 169	type_description, 264
where_, 170	qpp::exception::PermMismatchDims, 265
qpp::exception::InvalidIterator, 195	Exception, 266
Exception, 197	type_description, 266
type_description, 197	qpp::exception::QuditAlreadyMeasured, 312
qpp::exception::MatrixMismatchSubsys, 218	Exception, 313
Exception, 219	type_description, 314
type_description, 220	qpp::exception::SizeMismatch, 323
qpp::exception::MatrixNotCvector, 220	Exception, 324
Exception, 221	type_description, 324
type_description, 222	qpp::exception::SubsysMismatchDims, 335
qpp::exception::MatrixNotRvector, 222	Exception, 336
Exception, 223	type_description, 336

qpp::exception::TypeMismatch, 342 Exception, 343	end_, 205 first , 206
•	<del>_</del>
type_description, 344	IOManipRange, 204, 205
app::exception::UndefinedType, 344	last_, 206
Exception, 345	operator=, 205
type_description, 346	separator_, 206
qpp::exception::Unknown, 346	start_, 206
Exception, 347	qpp::internal::IOManipRange< InputIterator >, 203
type_description, 348	qpp::internal::Singleton
qpp::exception::ZeroSize, 352	~Singleton, 322
Exception, 353	get_instance, 322
type_description, 353	get_thread_local_instance, 322
qpp::experimental, 119	operator=, 322
qpp::internal, 119	Singleton, 321, 322
check_cvector, 120	qpp::internal::Singleton< T >, 320
check_dims, 120	qpp::is_complex< std::complex< T >>, 208
check_dims_match_cvect, 120	qpp::is_complex< T >, 207
check_dims_match_mat, 121	qpp::is_iterable< T, to_void< decltype(std::declval< T
check_dims_match_rvect, 121	$>$ ().begin()), decltype(std::declval $<$ T $>$ (). $\leftarrow$
check_eq_dims, 121	end()), decltype( $*$ (std::declval< T $>$ (). $\leftarrow$
check_matching_sizes, 121	begin()))>>, 210
check_no_duplicates, 121	qpp::is_iterable< T, typename >, 209
check_nonzero_size, 121	qpp::is_matrix_expression< Derived >, 211
check_perm, 122	qpp::literals, 125
check_qubit_cvector, 122	operator"" _bra, 125
check_qubit_matrix, 122	operator"" _i, 125
check_qubit_rvector, 122	operator"" _ket, 126
check_qubit_vector, 122	operator"" _prj, 126
check_rvector, 122	qpp::make_void
check_square_mat, 123	type, 218
check_subsys_match_dims, 123	qpp::make_void< Ts >, 217
check_vector, 123	QubitAmplitudeDampingNoise
dirsum2, 123	qpp::QubitAmplitudeDampingNoise, 304
get_dim_subsys, 123	QubitBitFlipNoise
get_num_subsys, 123	qpp::QubitBitFlipNoise, 305
kron2, 124	QubitBitPhaseFlipNoise
	qpp::QubitBitPhaseFlipNoise, 307
multiidx2n, 124	QubitDepolarizingNoise
n2multiidx, 124	qpp::QubitDepolarizingNoise, 308
variadic_vector_emplace, 124	QubitPhaseDampingNoise
qpp::internal::Display_Impl_, 152	qpp::QubitPhaseDampingNoise, 310
display_impl_, 152	QubitPhaseFlipNoise
qpp::internal::IOManipEigen, 197	qpp::QubitPhaseFlipNoise, 311
A_, 199	QuditDepolarizingNoise
chop_, 199	qpp::QuditDepolarizingNoise, 315
display, 199	
IOManipEigen, 199	rand
qpp::internal::IOManipPointer	qpp, 90–92
display, 201	qpp::Dynamic_bitset, 162, 163
end_, 202	randH
IOManipPointer, 201	qpp, 92
N_, 202	randidx
operator=, 202	qpp, <del>93</del>
p_, 202	randket
separator_, 202	qpp, 93
start_, 203	randkraus
qpp::internal::IOManipPointer< PointerType >, 200	qpp, 93
qpp::internal::IOManipRange	randn
display, 205	qpp, 94, 95

Fandom/Devices   app::Random/Devices   app	random h 206	achmidtaeaffa
randperm	random.h, 386	schmidtcoeffs
randperm		
app. 96         separator           qpp. 96         qpp. 96           randprob         qpp. 97           randdho         qpp. 97           randdho         qpp. 97           randU         qpp. 97           randU         qpp. 98           rgp. 98         qpp::QEngine, 300           reference         qpp::QCircuit::iterator, 216           qpp::Bit_circuit, 214         qpp::QEngine, 300           reny;         qpp::QEngine, 301           reset         qpp::Dynamic, bitset, 163           qpp::Bit_circuit, 132         qpp::Dynamic, bitset, 163           qpp. 99         qpp::Dynamic, bitset, 164           qpp::Dynamic, bitset, 163         qpp::Dynamic_bitset, 164           qpp::Dynamic, bitset, 163         qpp::Dynamic_bitset, 164           qpp::Dynamic, bitset, 163         qpp::Dynamic_bitset, 164           qpp::Dalloch         qpp::Dynamic_bitset, 164           qpp::Dynamic_bitset, 164         qpp::Dynamic_bitset, 164 <td></td> <td>·</td>		·
randprime	·	
randprob qpp, 97 randrho qpp, 97 randrho qpp, 97 randry qpp, 97 randry qpp, 97 randry qpp, 98 rd_ qpp:Gates, 179 RX qpp:Gates, 179 RX qpp:Gates, 180 RZ qpp:Gates, 180 SWAPd qpp:Bit_circuit; 133 qpp:Gates, 180 SWAPd qpp:Gates, 180 SWAPd qpp:Cates, 180 States qpp:Cates, 180 qpp:Timer, 241 qpp:Timer, 241 qpp:Timer, 241 qpp:Timer, 241 qpp:Timer, 241 qpp:Cates, 180 states qpp:Cates, 180 states qpp:Cates, 180 states qpp:Dynamic_bitset, 163 states qpp:Cates, 180 states qpp:Dynamic_bitset, 164 states qpp:Cates, 180 states		• —
randprob	·	
randrho		
randrho	•	
app, 97         app::QCircuit::iterator, 216           app, 97         app::QEngine, 300           randV         set_dit           app. 98         app::QEngine, 300           reference         app::QEngine, 301           app::QCircuit::iterator, 214         set_end.           rend         app::QEngine, 301           reset         app::QEngine, 301           signet         app::QEngine, 301           reset         signeton           app::Denci Licircuit, 132         app::Denci Licircuit, 321           app::Denci Licircuit, 132         app::Dynamic_bitset, 164           app::Dynamic_bitset, 163         spectralpown           app::Dynamic_bitset, 164         spectralpown           app::Dynamic_bitset, 164         spectralpown           app::Dynamic_bitset, 164         spectralpown           app::Dynamic_bitset, 164         app::Dynamic_bitset, 164           start		
randU		
app, 97         app::QEngine, 300           randV         set_end_           app. 98         app::QCircuit::iterator, 216           reference         set_measured_           app::QCircuit::iterator, 214         app::QEngine, 301           renyi         app. 106           sigma         app. 107           size         app. 107           size         app. 107           size         app. 107           size         app. 107           sqrtm         app. 108           start_         app. 108           start_         app. 108		
randV		
qpp; 98         qpp::QCircuit::iterator, 216           rd_ qpp::RandomDevices, 320         qpp::QEngine, 301           reference qpp::QCircuit::iterator, 214         qpp::QEngine, 301           renyi         qpp, 106           qpp::Bit_circuit, 132         qpp::Dynamic_bitset, 163           qpp::Dynamic_bitset, 163         qpp::Dynamic_bitset, 164           qpp. 99         spectralpowm           reshape         qpp::Dynamic_bitset, 164           qpp, 100         qpp. 107           reshape         qpp::Dynamic_bitset, 164           qpp, 100         qpp. 107           reshape         qpp::Dynamic_bitset, 164           qpp::Dates, 179         qpp::Timer, 341           qpp::Gates, 179         qpp::Timer, 341           qpp::Gates, 180         states           RZ         qpp::Gates, 180           RZ         qpp::Gates, 180           SWAPd         qpp::Dynamic_bitset, 164           qpp::Bype_qpp::Colorcuit, 272         storage_size           qpp::Dynamic_bitset, 165         storage_size           qpp::Dynamic_bitset, 165         storage_type           qpp::Dynamic_bitset, 165         storage_type           qpp::Dynamic_bitset, 165         storage_type           qpp::Dynamic_bitset, 165         sto		
rd_	app. 98	
qpp::RandomDevices, 320         qpp::CEngine, 301           reference         sigma           qpp::QCircuit::iterator, 214         qpp, 106           renyi         singleton           qpp;:Bit_circuit, 132         qpp::Dynamic_bitset, 163           qpp::Dynamic_bitset, 163         qpp. 107           qpp. 99         qpp.:Dynamic_bitset, 164           reshape         qpp. 100           qpp. 100         qpp. 107           Rn         qpp::Gates, 179           qpp::Gates, 179         qpp::Internal::IOManipPointer, 20           qpp::Gates, 180         statistics.h, 388           RZ         statistics.h, 388           qpp::Gates, 180         statistics.h, 388           StepType         qpp::Oricuit, 293           StepType         qpp::Dynamic_bitset, 164           qpp::Bit_circuit, 133         qpp::Dynamic_bitset, 165           qpp::Bit_circuit, 133         qpp::Dynamic_bitset, 165           qpp::Bit_circuit, 133         qpp::Dynamic_bitset, 165           qpp::Bqates, 184         storage_size           SWAP         qpp::Dynamic_bitset, 165           qpp::Bt_circuit, 133         qpp::Dynamic_bitset, 165           qpp::Bt_circuit, 133         qpp::Dynamic_bitset, 165           qpp::Dynamic_bitset, 165		
reference	<del>_</del>	<del>-</del> -
qpp;:QCircuit::iterator, 214         qpp, 106           renyi         qpp, 98, 99           reset         qpp::Bit_circuit, 132         qpp::Dynamic_bitset, 163           qpp;:QEngine, 300         qpp, 107           reshape         qpp, 100           qpp, 100         qpp, 107           rho2bloch         qpp, 100           qpp, 100         qpp, 108           rho2pure         qpp, 108           qpp::Gates, 179         qpp::Imer, 341           RN         qpp::Gates, 179           RY         states           qpp::Gates, 180         statistics, h, 388           RZ         qpp::Gates, 180           S         qpp::QCircuit, 293           StepType         qpp::QCircuit, 272           qpp::Gates, 180         storage_size           SWAPd         qpp::Bit_circuit, 133         qpp::Dynamic_bitset, 164           qpp::Bit_circuit;:Gate_count, 171         qpp::Dynamic_bitset, 165           qpp::Gates, 184         storage_size           qpp::Dynamic_bitset, 157         subsys_           qpp::Dynamic_bitset, 165         storage_type           qpp::Dynamic_bitset, 165         storage_type           qpp::Dynamic_bitset, 165         storage_type           qpp::Dynami		
renyi	gpp::QCircuit::iterator, 214	3
reset		
reset	•	<del>-</del>
qpp::Bit_circuit, 132         qpp.:107           qpp::Dynamic_bitset, 163         size           qpp::Dynamic_bitset, 164         spectralpowm           reshape         qpp, 100           qpp, 100         qpp, 107           Rn         qpp, 100           Rn         qpp::Timer, 341           qpp::Gates, 179         qpp::Internal::IOManipPointer, 20           qpp::Gates, 179         States           qpp::Gates, 180         statistics.h, 388           RZ         qpp::Gates, 180           RZ         qpp::Gates, 180           S         qpp::Qcircuit, 293           StepTypes         qpp::Qcircuit, 272           qpp::Gates, 184         storage_size           SWAPd         qpp::Dynamic_bitset, 164           qpp::Bit_circuit; 133         qpp::Dynamic_bitset, 165           qpp::Bit_circuit; 133         qpp::Dynamic_bitset, 165           qpp::Dynamic_bitset, 165         storage_type           qpp::Qengine, 302         sum           qpp::Qengine,	** *	
qpp::Dynamic_bitset, 163         size           qpp::QEngine, 300         qpp::Dynamic_bitset, 164           reshape         qpp. 107           qpp, 99         qpp, 107           rho2bloch         qpp, 100           qpp, 100         qpp::Timer, 341           qpp::Gates, 179         qpp::Internal::IOManipPointer, 20: qpp::Internal::IOManipRange, 20: qpp::Gates, 180           RZ         qpp::Gates, 180           RZ         qpp::Gates, 180           RZ         qpp::Gates, 180           S         statistics.h, 388           stepTypes         qpp::QCircuit, 293           StepType         qpp::QCircuit, 272           storage_size         qpp::Dynamic_bitset, 164           storage_size         qpp::Dynamic_bitset, 165           storage_type         qpp::Dynamic_bitset, 165           qpp::Bit_circuit; 133         qpp::Dynamic_bitset, 157           qpp::Bit_circuit::Gate_count, 171         qpp::Dynamic_bitset, 157           qpp, 101         qpp::Opp::QEngine, 302           save         qpp::Opp::QEngine, 302           sum         qpp::Opp::QEngine, 302           sum         qpp::Opp::Qengine, 302           starten         qpp::Opp::Qengine, 302           sum         qpp::Opp::Qengine, 302     <	qpp::Bit circuit, 132	
qpp::QEngine, 300         qpp::Dynamic_bitset, 164           reshape         qpp, 99           qpp, 100         qpp, 107           rho2bloch         qpp, 100           qpp, 100         qpp, 108           Rn         qpp::Timer, 341           qpp::Gates, 179         qpp::internal::IOManipPointer, 20           qpp::Gates, 179         qpp::states, 328           RY         qpp::Gates, 180         statistics.h, 388           RZ         qpp::Gates, 180         step_types_           S         qpp::Gates, 184         storage_size           SWAPd         qpp::Dynamic_bitset, 164           qpp::Bit_circuit; 133         qpp::Dynamic_bitset, 165           qpp::Bit_circuit::Gate_count, 171         qpp::Dynamic_bitset, 165           qpp::Bit_circuit::Gate_count, 171         qpp::Dynamic_bitset, 157           qpp::BandomDevices, 319         subsys_           save         qpp::Opy:Dynamic_bitset, 157           qpp, 101, 102         qpp, 108, 109           schatten         qpp, 109           qpp, 102         qpp, 110           schmidtA         qpp, 103           schmidtA         qpp, 100           qpp, 103         svdU		
reshape		
qpp, 99 rho2bloch qpp, 100 rho2pure qpp, 100 Rn qpp::Gates, 179 RY qpp::Gates, 180 RZ qpp::Gates, 180 RZ qpp::Gates, 180 SS RZ qpp::QCircuit, 293 Sterage_size qpp::Dynamic_bitset, 164 Storage_size qpp::Dynamic_bitset, 165 Storage_type qpp::Dynamic_bitset, 165 Storage_type qpp::Dynamic_bitset, 157 subsys_ storage_type qpp::QEngine, 302 SS RX qpp, 101 qpp::RandomDevices, 319 SaveMATLAB qpp, 101, 102 SchmidtA qpp, 103 SchmidtB SvdU		
rho2bloch         app, 100           qpp, 100         qpp, 108           Rn         app::Timer, 341           qpp::Gates, 179         qpp::internal::IOManipPointer, 20           RX         States           qpp::Gates, 179         statistics.h, 388           RY         statistics.h, 388           qpp::Gates, 180         step_types_           S         qpp::Qcircuit, 293           StepType         qpp::Qcircuit, 272           qpp::Gates, 184         storage_size           SWAPd         qpp::Dynamic_bitset, 164           dpp::Bit_circuit, 133         storage_lype           qpp::Bypamic_bitset, 165         qpp::Dynamic_bitset, 165           save         qpp::Dynamic_bitset, 157           qpp::Gates, 184         subsys_           save         qpp::Dynamic_bitset, 157           qpp::Gates, 184         subsys_           save         qpp::Dynamic_bitset, 157           subsys_         subsys_           qpp::RandomDevices, 319         qpp, 108, 109           saveMATLAB         qpp, 109           qpp, 101         qpp, 109           schatten         qpp, 109           qpp, 102         qpp, 110           schmidtA         qpp, 110	•	
qpp, 100       qpp, 108         rho2pure       start		
rho2pure	qpp, 100	·
qpp, 100         qpp::Timer, 341           qpp::Gates, 179         qpp::internal::IOManipPointer, 20           qpp::Gates, 179         States           qpp::Gates, 179         qpp::States, 328           RY         statistics.h, 388           RZ         qpp::Gates, 180           RZ         qpp::QCircuit, 293           Qpp::Gates, 180         StepType           SWAPd         qpp::Dynamic_bitset, 164           qpp::Bit_circuit, 133         qpp::Dynamic_bitset, 165           qpp::Bit_circuit; Gate_count, 171         qpp::Dynamic_bitset, 157           qpp::Gates, 184         storage_size           save         qpp::Dynamic_bitset, 157           qpp::Gates, 184         subsys_           save         qpp::Dynamic_bitset, 157           qpp::Gates, 184         subsys_           save         qpp::Dynamic_bitset, 157           qpp::Dynamic_bitset, 165         subsys_           save         qpp::Dynamic_bitset, 165           save         qpp::Dynamic_bitset, 165           subsys_         subsys_           save         qpp::Dynamic_bitset, 165           subsys_         subsys_           save         qpp::Dynamic_bitset, 165           subsys_         subsys_ </td <td></td> <td></td>		
## App::Gates, 179 ## App::Internal::IOManipPointer, 200	•	<del>_</del>
qpp::Gates, 179       qpp::internal::IOManipRange, 206         RY       qpp::Gates, 328         qpp::Gates, 180       statistics.h, 388         RZ       qpp::QCircuit, 293         qpp::Gates, 180       Step_types		
RX       qpp::Gates, 179       States         RY       qpp::Gates, 328         qpp::Gates, 180       step_types_         qpp::Gates, 180       qpp::QCircuit, 293         S       qpp::QCircuit, 272         storage_size       qpp::Dynamic_bitset, 164         SWAPd       qpp::Dynamic_bitset, 165         qpp::Bit_circuit, 133       storage_size         qpp::Bit_circuit::Gate_count, 171       qpp::Dynamic_bitset, 157         qpp::Gates, 184       subsys_         save       qpp::QEngine, 302         qpp, 101       sum         qpp, 104       qpp, 108, 109         saveMATLAB       qpp, 108, 109         qpp, 101, 102       qpp, 109         schatten       svals         qpp, 102       qpp, 110         schmidtA       qpp, 103         schmidtB       svdU	qpp::Gates, 179	
qpp::Gates, 179       qpp::States, 328         RY       statistics.h, 388         qpp::Gates, 180       step_types_         qpp::Gates, 180       qpp::QCircuit, 293         StepType       qpp::QCircuit, 272         qpp::Gates, 184       storage_size         SWAPd       qpp::Dynamic_bitset, 164         qpp::Gates, 180       storage_size_         SWAP       qpp::Dynamic_bitset, 165         qpp::Bit_circuit, 133       storage_type         qpp::Bynamic_bitset, 165       storage_type         qpp::Dynamic_bitset, 157       qpp::Dynamic_bitset, 157         save       qpp::QEngine, 302         sum       qpp, 101         qpp, 101       sum         qpp, 108, 109       super2choi         qpp, 109, 100       qpp, 109         schatten       svals         qpp, 102       qpp, 110         schmidtA       svd         qpp, 103       qpp, 110         schmidtB       svdU		
## app::Gates, 180	qpp::Gates, 179	
RZ       step_types_         qpp::Gates, 180       step_types_         S       qpp::QCircuit, 272         qpp::Gates, 184       storage_size         SWAPd       qpp::Dynamic_bitset, 164         qpp::Bit_circuit, 133       qpp::Dynamic_bitset, 165         qpp::Bit_circuit::Gate_count, 171       qpp::Dynamic_bitset, 157         qpp::Gates, 184       subsys_         save       qpp::QEngine, 302         qpp, 101       sum         qpp, 101, 102       super:Zchoi         saveMATLAB       super:Zchoi         qpp, 101, 102       qpp, 109         schatten       svals         qpp, 102       qpp, 110         schmidtA       qpp, 103         schmidtB       svdU	RY	
RZ       qpp::Gates, 180       StepType         S       qpp::QCircuit, 272         qpp::Gates, 184       storage_size         SWAPd       qpp::Dynamic_bitset, 164         qpp::Gates, 180       storage_size_         SWAP       qpp::Dynamic_bitset, 165         qpp::Bit_circuit, 133       storage_type         qpp::Bit_circuit::Gate_count, 171       qpp::Dynamic_bitset, 157         qpp::Gates, 184       subsys_         save       qpp::QEngine, 302         qpp, 101       sum         qpp::RandomDevices, 319       qpp, 108, 109         saveMATLAB       super2choi         qpp, 101, 102       qpp, 109         schatten       svals         qpp, 102       qpp, 110         schmidtA       qpp, 110         qpp, 103       qpp, 110         schmidtB       svdU	qpp::Gates, 180	
S         StepType           qpp::Gates, 184         storage_size           SWAPd         qpp::Dynamic_bitset, 164           qpp::Gates, 180         storage_size_           SWAP         qpp::Dynamic_bitset, 165           qpp::Bit_circuit, 133         storage_type           qpp::Bit_circuit::Gate_count, 171         qpp::Dynamic_bitset, 157           qpp::Gates, 184         subsys_           save         qpp::QEngine, 302           qpp, 101         sum           qpp::RandomDevices, 319         qpp, 108, 109           saveMATLAB         super2choi           qpp, 101, 102         qpp, 109           schatten         svals           qpp, 102         qpp, 110           schmidtA         svd           qpp, 103         qpp, 110           schmidtB         svdU		
S       qpp::QCircuit, 272         qpp::Gates, 184       storage_size         SWAPd       qpp::Dynamic_bitset, 164         qpp::Gates, 180       storage_size_         SWAP       qpp::Dynamic_bitset, 165         qpp::Bit_circuit, 133       storage_type         qpp::Dynamic_bitset, 157       qpp::Dynamic_bitset, 157         save       qpp::QEngine, 302         qpp, 101       sum         qpp::QEngine, 302       sum         saveMATLAB       super2choi         qpp, 101, 102       qpp, 109         schatten       svals         qpp, 102       qpp, 110         schmidtA       svd         qpp, 103       qpp, 110         schmidtB       svdU	qpp::Gates, 180	
qpp::Gates, 184       storage_size         SWAPd       qpp::Dynamic_bitset, 164         qpp::Gates, 180       storage_size_         SWAP       qpp::Dynamic_bitset, 165         qpp::Bit_circuit, 133       storage_type         qpp::Bit_circuit::Gate_count, 171       qpp::Dynamic_bitset, 157         qpp::Gates, 184       subsys_         save       qpp::QEngine, 302         qpp, 101       sum         qpp::RandomDevices, 319       super:QEngine, 302         saveMATLAB       super:2choi         qpp, 101, 102       qpp, 109         schatten       svals         qpp, 102       qpp, 110         schmidtA       svd         qpp, 103       qpp, 110         schmidtB       svdU		
SWAPd qpp::Dynamic_bitset, 164 qpp::Gates, 180 storage_size_ qpp::Dynamic_bitset, 165  qpp::Bit_circuit, 133 qpp::Bit_circuit::Gate_count, 171 qpp::Dynamic_bitset, 157  qpp::Gates, 184 subsys_ qpp, 101 sum qpp::RandomDevices, 319 qpp, 108, 109  saveMATLAB qpp, 101, 102 qpp, 109  schatten qpp, 102 qpp, 109  schatten qpp, 102 qpp, 110  schmidtA svd qpp, 103  schmidtB svdU	S	
app::Gates, 180       storage_size_         SWAP       qpp::Dynamic_bitset, 165         app::Bit_circuit, 133       storage_type         app::Bit_circuit::Gate_count, 171       app::Dynamic_bitset, 157         app::Gates, 184       subsys_         save       app::QEngine, 302         app, 101       sum         app::RandomDevices, 319       app, 108, 109         saveMATLAB       super2choi         app, 101, 102       app, 109         schatten       svals         app, 102       app, 110         schmidtA       svd         app, 103       app, 110         schmidtB       svdU		<del>-</del> —
SWAP		
qpp::Bit_circuit, 133       storage_type         qpp::Bit_circuit::Gate_count, 171       qpp::Dynamic_bitset, 157         qpp::Gates, 184       subsys		<b>y</b> – –
qpp::Bit_circuit::Gate_count, 171       qpp::Dynamic_bitset, 157         qpp::Gates, 184       subsys_         save       qpp::QEngine, 302         qpp, 101       sum         qpp::RandomDevices, 319       qpp, 108, 109         saveMATLAB       super2choi         qpp, 101, 102       qpp, 109         schatten       svals         qpp, 102       qpp, 110         schmidtA       svd         qpp, 103       qpp, 110         schmidtB       svdU		
qpp::Gates, 184       subsys_         save       qpp::QEngine, 302         qpp, 101       sum         qpp::RandomDevices, 319       qpp, 108, 109         saveMATLAB       super2choi         qpp, 101, 102       qpp, 109         schatten       svals         qpp, 102       qpp, 110         schmidtA       svd         qpp, 103       qpp, 110         schmidtB       svdU	<u> </u>	0 = 71
save       qpp::QEngine, 302         qpp, 101       sum         qpp::RandomDevices, 319       qpp, 108, 109         saveMATLAB       super2choi         qpp, 101, 102       qpp, 109         schatten       svals         qpp, 102       qpp, 110         schmidtA       svd         qpp, 103       qpp, 110         schmidtB       svdU		
qpp, 101       sum         qpp::RandomDevices, 319       qpp, 108, 109         saveMATLAB       super2choi         qpp, 101, 102       qpp, 109         schatten       svals         qpp, 102       qpp, 110         schmidtA       svd         qpp, 103       qpp, 110         schmidtB       svdU	qpp::Gates, 184	<i>,</i> –
qpp::RandomDevices, 319       qpp, 108, 109         saveMATLAB       super2choi         qpp, 101, 102       qpp, 109         schatten       svals         qpp, 102       qpp, 110         schmidtA       svd         qpp, 103       qpp, 110         schmidtB       svdU		
saveMATLAB         super2choi           qpp, 101, 102         qpp, 109           schatten         svals           qpp, 102         qpp, 110           schmidtA         svd           qpp, 103         qpp, 110           schmidtB         svdU		
qpp, 101, 102       qpp, 109         schatten       svals         qpp, 102       qpp, 110         schmidtA       svd         qpp, 103       qpp, 110         schmidtB       svdU		
schatten         svals           qpp, 102         qpp, 110           schmidtA         svd           qpp, 103         qpp, 110           schmidtB         svdU		•
qpp, 102       qpp, 110         schmidtA       svd         qpp, 103       qpp, 110         schmidtB       svdU		
schmidtA         svd           qpp, 103         qpp, 110           schmidtB         svdU		
qpp, 103         qpp, 110           schmidtB         svdU		
schmidtB svdU		
qpp, 103, 104 qpp, 110		
	qpp, 103, 104	qpp, 110

svdV	qpp::exception::MatrixNotRvector, 224
qpp, 111	qpp::exception::MatrixNotSquare, 226
syspermute	qpp::exception::MatrixNotSquareNorCvector, 228
qpp, 111, 112	qpp::exception::MatrixNotSquareNorRvector, 230
Т	qpp::exception::MatrixNotSquareNorVector, 232
	qpp::exception::MatrixNotVector, 234
qpp::Gates, 184 TFQ	qpp::exception::NoCodeword, 239
	qpp::exception::NotBipartite, 248
qpp, 112	qpp::exception::NotImplemented, 250
qpp::QCircuit, 289 TOF	qpp::exception::NotQubitCvector, 252
	qpp::exception::NotQubitMatrix, 254
qpp::Bit_circuit, 133	qpp::exception::NotQubitRvector, 256
qpp::Bit_circuit::Gate_count, 171	qpp::exception::NotQubitSubsys, 258
qpp::Gates, 184	qpp::exception::NotQubitVector, 260
target_	qpp::exception::OutOfRange, 262
qpp::QCircuit::GateStep, 187	qpp::exception::PermInvalid, 264
qpp::QCircuit::MeasureStep, 236	qpp::exception::PermMismatchDims, 266
tic	qpp::exception::QuditAlreadyMeasured, 314
qpp::Timer, 340	qpp::exception::SizeMismatch, 324
tics	qpp::exception::SubsysMismatchDims, 336
qpp::Timer, 341	qpp::exception::TypeMismatch, 344
Timer	qpp::exception::UndefinedType, 346
qpp::Timer, 338, 339	qpp::exception::Unknown, 348
to_JSON	qpp::exception::ZeroSize, 353
qpp::IJSON, 193	types.h, 390
qpp::QCircuit, 289	
qpp::QEngine, 301	uniform
to_string	qpp, 114
qpp::Dynamic_bitset, 164	
to_void	V_
qpp, 28	qpp::Dynamic_bitset, 165
toc	value_type
qpp::Timer, 341	qpp::Dynamic_bitset, 157
trace	qpp::QCircuit::iterator, 214
qpp, 112	value_type_
traits.h, 389	qpp::QCircuit::iterator::value_type_, 349
transpose	value_type_qcd_
qpp, 113	<pre>qpp::QCircuit::iterator::value_type_, 351</pre>
tsallis	var
qpp, 113, 114	qpp, 115
Туре	variadic_vector_emplace
qpp::Codes, 135	qpp::internal, 124
type	
qpp::make_void, 218	W
type_	qpp::States, 333
qpp::QCircuit::iterator::value_type_, 351	what
type_description	qpp::exception::Exception, 169
qpp::exception::CustomException, 139	what_
qpp::exception::DimsInvalid, 141	qpp::exception::CustomException, 139
qpp::exception::DimsMismatchCvector, 143	where_
qpp::exception::DimsMismatchMatrix, 145	qpp::exception::Exception, 170
qpp::exception::DimsMismatchRvector, 147	
qpp::exception::DimsMismatchVector, 149	X
qpp::exception::DimsNotEqual, 151	qpp::Bit_circuit, 133
qpp::exception::Duplicates, 154	qpp::Bit_circuit::Gate_count, 171
qpp::exception::Exception, 169	qpp::Gates, 184
qpp::exception::InvalidIterator, 197	x0
qpp::exception::MatrixMismatchSubsys, 220	qpp::States, 333
qpp::exception::MatrixNotCvector, 222	x1
/	

```
qpp::States, 334
x2contfrac
     qpp, 115
Χd
     qpp::Gates, 182
Υ
     qpp::Gates, 185
y0
     qpp::States, 334
у1
     qpp::States, 334
Ζ
     qpp::Gates, 185
z0
     qpp::States, 334
z1
     qpp::States, 334
\operatorname{\mathsf{Zd}}
     qpp::Gates, 182
zero
     qpp::States, 330
```