Quantum++ v1.1

Generated by Doxygen 1.8.13

Contents

1	Qua	ntum++															1
2	Nam	nespace	Index														3
	2.1	Names	space List					 	 	 	 		 			 	 3
3	Hier	archica	l Index														5
	3.1	Class	Hierarchy					 	 	 	 		 			 	 5
4	Clas	s Index															7
	4.1	Class	List					 	 	 	 		 			 	 7
5	File	Index															11
	5.1	File Lis	st					 	 	 	 		 			 	 11
6	Nam	nespace	Docume	ntat	tion												13
	6.1	qpp Na	amespace	Ref	feren	ice .		 	 	 	 		 			 	 13
		6.1.1	Detailed	Des	script	tion		 	 	 	 		 			 	 26
		6.1.2	Typedef	Doc	ume	ntatio	on .	 	 	 	 		 			 	 26
			6.1.2.1	bi	gint			 	 	 	 		 			 	 26
			6.1.2.2	br	a.			 	 	 	 		 			 	 26
			6.1.2.3	cr	nat			 	 	 	 		 			 	 26
			6.1.2.4	cp	olx .			 	 	 	 		 			 	 26
			6.1.2.5	dr	mat			 	 	 	 		 			 	 27
			6.1.2.6	dy	yn_co	ol_ve	ct .	 	 	 	 		 			 	 27
			6.1.2.7	dy	yn_m	at .		 	 	 	 		 			 	 27
			6.1.2.8	d١	vn ro	W V	ect	 	 	 	 		 			 	 27

ii CONTENTS

	6.1.2.9	idx	. 28
	6.1.2.10	ket	. 28
	6.1.2.11	to_void	. 28
6.1.3	Function	Documentation	. 28
	6.1.3.1	absm()	. 28
	6.1.3.2	abssq() [1/3]	. 29
	6.1.3.3	abssq() [2/3]	. 29
	6.1.3.4	abssq() [3/3]	. 29
	6.1.3.5	adjoint()	. 30
	6.1.3.6	anticomm()	. 30
	6.1.3.7	apply() [1/5]	. 31
	6.1.3.8	apply() [2/5]	. 31
	6.1.3.9	apply() [3/5]	. 32
	6.1.3.10	apply() [4/5]	. 32
	6.1.3.11	apply() [5/5]	. 33
	6.1.3.12	applyCTRL() [1/2]	. 33
	6.1.3.13	applyCTRL() [2/2]	. 34
	6.1.3.14	applyQFT()	. 34
	6.1.3.15	applyTFQ()	. 35
	6.1.3.16	avg()	. 35
	6.1.3.17	bloch2rho()	. 36
	6.1.3.18	choi2kraus()	. 36
	6.1.3.19	choi2super()	. 37
	6.1.3.20	comm()	. 37
	6.1.3.21	complement()	. 38
	6.1.3.22	compperm()	. 38
	6.1.3.23	concurrence()	. 38
	6.1.3.24	conjugate()	. 40
	6.1.3.25	contfrac2x()	. 40
	6.1.3.26	convergents() [1/2]	. 41

CONTENTS

6.1.3.27	convergents() [2/2]	41
6.1.3.28	cor()	42
6.1.3.29	cosm()	42
6.1.3.30	cov()	43
6.1.3.31	cwise()	43
6.1.3.32	det()	43
6.1.3.33	dirsum() [1/4]	44
6.1.3.34	dirsum() [2/4]	44
6.1.3.35	dirsum() [3/4]	45
6.1.3.36	dirsum() [4/4]	45
6.1.3.37	dirsumpow()	46
6.1.3.38	disp() [1/5]	46
6.1.3.39	disp() [2/5]	47
6.1.3.40	disp() [3/5]	47
6.1.3.41	disp() [4/5]	48
6.1.3.42	disp() [5/5]	48
6.1.3.43	egcd()	49
6.1.3.44	eig()	49
6.1.3.45	entanglement() [1/2]	49
6.1.3.46	entanglement() [2/2]	50
6.1.3.47	entropy() [1/2]	51
6.1.3.48	entropy() [2/2]	51
6.1.3.49	evals()	51
6.1.3.50	evects()	52
6.1.3.51	expm()	52
6.1.3.52	factors()	53
6.1.3.53	funm()	53
6.1.3.54	gcd() [1/2]	53
6.1.3.55	gcd() [2/2]	54
6.1.3.56	gconcurrence()	54

iv CONTENTS

6.1.3.57	grams() [1/3]	55
6.1.3.58	grams() [2/3]	55
6.1.3.59	grams() [3/3]	56
6.1.3.60	heig()	56
6.1.3.61	hevals()	56
6.1.3.62	hevects()	57
6.1.3.63	inverse()	57
6.1.3.64	invperm()	58
6.1.3.65	ip() [1/2]	58
6.1.3.66	ip() [2/2]	58
6.1.3.67	isprime()	59
6.1.3.68	kraus2choi()	59
6.1.3.69	kraus2super()	60
6.1.3.70	kron() [1/4]	60
6.1.3.71	kron() [2/4]	61
6.1.3.72	kron() [3/4]	61
6.1.3.73	kron() [4/4]	62
6.1.3.74	kronpow()	62
6.1.3.75	lcm() [1/2]	63
6.1.3.76	lcm() [2/2]	63
6.1.3.77	load()	64
6.1.3.78	loadMATLAB() [1/2]	64
6.1.3.79	loadMATLAB() [2/2]	65
6.1.3.80	logdet()	66
6.1.3.81	logm()	66
6.1.3.82	lognegativity() [1/2]	66
6.1.3.83	lognegativity() [2/2]	67
6.1.3.84	marginalX()	67
6.1.3.85	marginalY()	67
6.1.3.86	measure() [1/9]	68

CONTENTS

6.1.3.87 measure() [2/9]	8
6.1.3.88 measure() [3/9]	59
6.1.3.89 measure() [4/9]	69
6.1.3.90 measure() [5/9]	70
6.1.3.91 measure() [6/9]	71
6.1.3.92 measure() [7/9]	71
6.1.3.93 measure() [8/9]	72
6.1.3.94 measure() [9/9]	73
6.1.3.95 measure_seq() [1/2]	73
6.1.3.96 measure_seq() [2/2]	74
6.1.3.97 mket() [1/2]	74
6.1.3.98 mket() [2/2]	75
6.1.3.99 modinv()	75
6.1.3.100 modmul()	76
6.1.3.101 modpow()	76
6.1.3.102 mprj() [1/2]	77
6.1.3.103 mprj() [2/2]	77
6.1.3.104 multiidx2n()	78
6.1.3.105 n2multiidx()	78
6.1.3.106 negativity() [1/2]	79
6.1.3.107 negativity() [2/2]	79
6.1.3.108 norm()	30
6.1.3.109 omega()	30
6.1.3.110 operator""" _i()	30
6.1.3.111 powm()	31
6.1.3.112 prj()	31
6.1.3.113 prod() [1/3]	32
6.1.3.114 prod() [2/3]	32
6.1.3.115 prod() [3/3]	32
6.1.3.116 ptrace() [1/2] 8	33

vi

6.1.3.117 ptrace() [2/2]	33
6.1.3.118 ptrace1() [1/2] 8	34
6.1.3.119 ptrace1() [2/2] 8	34
6.1.3.120 ptrace2() [1/2] 8	36
6.1.3.121 ptrace2() [2/2] 8	36
6.1.3.122 ptranspose() [1/2]	37
6.1.3.123 ptranspose() [2/2]	37
6.1.3.124 QFT()	38
6.1.3.125 qmutualinfo() [1/2]	38
6.1.3.126 qmutualinfo() [2/2]	39
6.1.3.127 rand() [1/5]	39
6.1.3.128 rand() [2/5] 9	90
6.1.3.129 rand() [3/5]	90
6.1.3.130 rand() [4/5]	90
6.1.3.131 rand() [5/5] 9	91
6.1.3.132 randH()	91
6.1.3.133 randidx()	93
6.1.3.134 randket()	93
6.1.3.135 randkraus()	94
6.1.3.136 randn() [1/4] 9	94
6.1.3.137 randn() [2/4] 9	94
6.1.3.138 randn() [3/4] 9	95
6.1.3.139 randn() [4/4] 9	95
6.1.3.140 randperm()	96
6.1.3.141 randprime()	96
6.1.3.142 randprob()	97
6.1.3.143 randrho()	97
6.1.3.144 randU()	97
6.1.3.145 randV()	98
6.1.3.146 renyi() [1/2]	98

CONTENTS vii

6.1.3.147 renyi() [2/2]
6.1.3.148 reshape()
6.1.3.149 rho2bloch()
6.1.3.150 rho2pure()
6.1.3.151 save()
6.1.3.152 saveMATLAB() [1/2]
6.1.3.153 saveMATLAB() [2/2] 102
6.1.3.154 schatten()
6.1.3.155 schmidtA() [1/2]
6.1.3.156 schmidtA() [2/2]
6.1.3.157 schmidtB() [1/2]
6.1.3.158 schmidtB() [2/2]
6.1.3.159 schmidtcoeffs() [1/2] 104
6.1.3.160 schmidtcoeffs() [2/2] 105
6.1.3.161 schmidtprobs() [1/2] 105
6.1.3.162 schmidtprobs() [2/2] 106
6.1.3.163 sigma()
6.1.3.164 sinm()
6.1.3.165 spectralpowm()
6.1.3.166 sqrtm()
6.1.3.167 sum() [1/3]
6.1.3.168 sum() [2/3]
6.1.3.169 sum() [3/3]
6.1.3.170 super2choi()
6.1.3.171 svals()
6.1.3.172 svd()
6.1.3.173 svdU()
6.1.3.174 svdV()
6.1.3.175 syspermute() [1/2]
6.1.3.176 syspermute() [2/2]

viii CONTENTS

		6.1.3.177	7 TFQ()	 112
		6.1.3.178	3 trace()	 113
		6.1.3.179	9 transpose()	 113
		6.1.3.180	O tsallis() [1/2]	 113
		6.1.3.181	1 tsallis() [2/2]	 114
		6.1.3.182	2 uniform()	 114
		6.1.3.183	3 var()	 115
		6.1.3.184	4 x2contfrac()	 115
	6.1.4	Variable	Documentation	 116
		6.1.4.1	chop	 116
		6.1.4.2	ee	 116
		6.1.4.3	eps	 116
		6.1.4.4	idx_infty	 116
		6.1.4.5	infty	 116
		6.1.4.6	maxn	 117
		6.1.4.7	pi	 117
6.2	qpp::ex	ception N	amespace Reference	 117
	6.2.1	Detailed	Description	 118
6.3	qpp::ex	perimenta	al Namespace Reference	 119
	6.3.1	Detailed	Description	 119
6.4	qpp::in	ternal Nan	nespace Reference	 119
	6.4.1	Detailed	Description	 120
	6.4.2	Function	Documentation	 120
		6.4.2.1	check_cvector()	 120
		6.4.2.2	check_dims()	 120
		6.4.2.3	check_dims_match_cvect()	 121
		6.4.2.4	check_dims_match_mat()	 121
		6.4.2.5	check_dims_match_rvect()	 121
		6.4.2.6	check_eq_dims()	 121
		6.4.2.7	check_matching_sizes()	 121

CONTENTS

		6.4.2.8	check_no_duplicates()	 121
		6.4.2.9	check_nonzero_size()	 122
		6.4.2.10	check_perm()	 122
		6.4.2.11	check_qubit_cvector()	 122
		6.4.2.12	check_qubit_matrix()	 122
		6.4.2.13	check_qubit_rvector()	 122
		6.4.2.14	check_qubit_vector()	 122
		6.4.2.15	check_rvector()	 123
		6.4.2.16	check_square_mat()	 123
		6.4.2.17	check_subsys_match_dims()	 123
		6.4.2.18	check_vector()	 123
		6.4.2.19	dirsum2()	 123
		6.4.2.20	get_dim_subsys()	 123
		6.4.2.21	get_num_subsys()	 124
		6.4.2.22	kron2()	 124
		6.4.2.23	multiidx2n()	 124
		6.4.2.24	n2multiidx()	 124
		6.4.2.25	variadic_vector_emplace() [1/2]	 124
		6.4.2.26	variadic_vector_emplace() [2/2]	 124
6.5	qpp::lit	erals Nam	nespace Reference	 125
	6.5.1	Function	Documentation	 125
		6.5.1.1	operator""""_bra()	 125
		6.5.1.2	operator""""_i()	 125
		6.5.1.3	operator""""_ket()	 126
		6.5.1.4	operator"""" _prj()	 126

CONTENTS

7	Clas	s Docu	mentation	129
	7.1	qpp::B	t_circuit Class Reference	129
		7.1.1	Detailed Description	131
		7.1.2	Constructor & Destructor Documentation	131
			7.1.2.1 Bit_circuit()	131
		7.1.3	Member Function Documentation	131
			7.1.3.1 CNOT()	131
			7.1.3.2 FRED()	131
			7.1.3.3 NOT()	132
			7.1.3.4 reset()	132
			7.1.3.5 SWAP()	132
			7.1.3.6 TOF()	133
			7.1.3.7 X()	133
		7.1.4	Member Data Documentation	134
			7.1.4.1 gate_count	134
	7.2	qpp::C	odes Class Reference	134
		7.2.1	Detailed Description	135
		7.2.2	Member Enumeration Documentation	135
			7.2.2.1 Type	135
		7.2.3	Constructor & Destructor Documentation	136
			7.2.3.1 Codes()	136
			7.2.3.2 ~Codes()	136
		7.2.4	Member Function Documentation	136
			7.2.4.1 codeword()	136
		7.2.5	Friends And Related Function Documentation	136
			7.2.5.1 internal::Singleton < const Codes >	137
	7.3	qpp::ex	cception::CustomException Class Reference	137
		7.3.1	Detailed Description	138
		7.3.2	Constructor & Destructor Documentation	138
			7.3.2.1 CustomException()	139

CONTENTS xi

	7.3.3	Member Function Documentation
		7.3.3.1 type_description()
	7.3.4	Member Data Documentation
		7.3.4.1 what
7.4	qpp::ex	cception::DimsInvalid Class Reference
	7.4.1	Detailed Description
	7.4.2	Member Function Documentation
		7.4.2.1 type_description()
7.5	qpp::ex	cception::DimsMismatchCvector Class Reference
	7.5.1	Detailed Description
	7.5.2	Member Function Documentation
		7.5.2.1 type_description()
7.6	qpp::ex	cception::DimsMismatchMatrix Class Reference
	7.6.1	Detailed Description
	7.6.2	Member Function Documentation
		7.6.2.1 type_description()
7.7	qpp::ex	cception::DimsMismatchRvector Class Reference
	7.7.1	Detailed Description
	7.7.2	Member Function Documentation
		7.7.2.1 type_description()
7.8	qpp::ex	cception::DimsMismatchVector Class Reference
	7.8.1	Detailed Description
	7.8.2	Member Function Documentation
		7.8.2.1 type_description()
7.9	qpp::ex	cception::DimsNotEqual Class Reference
	7.9.1	Detailed Description
	7.9.2	Member Function Documentation
		7.9.2.1 type_description()
7.10	qpp::in	ternal::Display_Impl_ Struct Reference
	7.10.1	Member Function Documentation

xii CONTENTS

		7.10.1.1 display_impl_()	151
7.11	qpp::ex	ception::Duplicates Class Reference	152
	7.11.1	Detailed Description	153
	7.11.2	Member Function Documentation	153
		7.11.2.1 type_description()	153
7.12	qpp::D	namic_bitset Class Reference	153
	7.12.1	Detailed Description	155
	7.12.2	Member Typedef Documentation	156
		7.12.2.1 storage_type	156
		7.12.2.2 value_type	156
	7.12.3	Constructor & Destructor Documentation	156
		7.12.3.1 Dynamic_bitset()	156
	7.12.4	Member Function Documentation	156
		7.12.4.1 all()	156
		7.12.4.2 any()	157
		7.12.4.3 count()	157
		7.12.4.4 data()	157
		7.12.4.5 display()	157
		7.12.4.6 flip() [1/2]	158
		7.12.4.7 flip() [2/2]	158
		7.12.4.8 get()	158
		7.12.4.9 index_()	159
		7.12.4.10 none()	159
		7.12.4.11 offset_()	159
		7.12.4.12 operator"!=()	160
		7.12.4.13 operator-()	160
		7.12.4.14 operator==()	160
		7.12.4.15 rand() [1/2]	161
		7.12.4.16 rand() [2/2] 1	161
		7.12.4.17 reset() [1/2]	162

CONTENTS xiii

		7.12.4.18 reset() [2/2]	32
		7.12.4.19 set() [1/2]	62
		7.12.4.20 set() [2/2]	63
		7.12.4.21 size()	63
		7.12.4.22 storage_size()	63
		7.12.4.23 to_string()	63
	7.12.5	Member Data Documentation	64
		7.12.5.1 N	64
		7.12.5.2 storage_size	34
		7.12.5.3 v	34
7.13	qpp::ex	cception::Exception Class Reference	35
	7.13.1	Detailed Description	36
	7.13.2	Constructor & Destructor Documentation	37
		7.13.2.1 Exception()	37
	7.13.3	Member Function Documentation	37
		7.13.3.1 type_description()	37
		7.13.3.2 what()	38
	7.13.4	Member Data Documentation	38
		7.13.4.1 msg	38
		7.13.4.2 where	38
7.14	qpp::Bi	t_circuit::Gate_count Struct Reference	38
	7.14.1	Member Data Documentation	69
		7.14.1.1 CNOT	39
		7.14.1.2 FRED	39
		7.14.1.3 NOT	39
		7.14.1.4 SWAP	39
		7.14.1.5 TOF	39
		7.14.1.6 X	70
7.15	qpp::Ga	ates Class Reference	70
	7.15.1	Detailed Description	72

xiv CONTENTS

7.15.2	Constructor & Destructor Documentation
	7.15.2.1 Gates()
	7.15.2.2 ~Gates()
7.15.3	Member Function Documentation
	7.15.3.1 CTRL()
	7.15.3.2 expandout() [1/3]
	7.15.3.3 expandout() [2/3]
	7.15.3.4 expandout() [3/3]
	7.15.3.5 Fd()
	7.15.3.6 get_name()
	7.15.3.7 ld()
	7.15.3.8 MODMUL()
	7.15.3.9 Rn()
	7.15.3.10 RX()
	7.15.3.11 RY()
	7.15.3.12 RZ()
	7.15.3.13 SWAPd()
	7.15.3.14 Xd()
	7.15.3.15 Zd()
7.15.4	Friends And Related Function Documentation
	7.15.4.1 internal::Singleton< const Gates >
7.15.5	Member Data Documentation
	7.15.5.1 CNOT
	7.15.5.2 CNOTba
	7.15.5.3 CZ
	7.15.5.4 FRED
	7.15.5.5 H
	7.15.5.6 ld2
	7.15.5.7 S
	7.15.5.8 SWAP

CONTENTS xv

		7.15.5.9 T	1
		7.15.5.10 TOF	2
		7.15.5.11 X	2
		7.15.5.12 Y	2
		7.15.5.13 Z	2
7.16	qpp::Q0	CircuitDescription::GateStep Struct Reference	3
7	7.16.1	Detailed Description	4
7	7.16.2	Constructor & Destructor Documentation	4
		7.16.2.1 GateStep() [1/2]	4
		7.16.2.2 GateStep() [2/2]	4
7	7.16.3	Member Data Documentation	4
		7.16.3.1 ctrl	4
		7.16.3.2 gate	5
		7.16.3.3 gate_type	5
		7.16.3.4 name	5
		7.16.3.5 step_no	5
		7.16.3.6 target	5
7.17 c	pp::ID	risplay Class Reference	6
7	7.17.1	Detailed Description	7
7	7.17.2	Constructor & Destructor Documentation	7
		7.17.2.1 IDisplay() [1/3]	7
		7.17.2.2 IDisplay() [2/3]	7
		7.17.2.3 IDisplay() [3/3]	7
		7.17.2.4 ~IDisplay()	7
7	7.17.3	Member Function Documentation	8
		7.17.3.1 display()	8
		7.17.3.2 operator=() [1/2]	8
		7.17.3.3 operator=() [2/2]	8
7	7.17.4	Friends And Related Function Documentation	8
		7.17.4.1 operator<< 18	8

xvi CONTENTS

7.18	qpp::In	it Class Reference	189
	7.18.1	Detailed Description	190
	7.18.2	Constructor & Destructor Documentation	190
		7.18.2.1 Init()	190
		7.18.2.2 ~Init()	190
	7.18.3	Friends And Related Function Documentation	190
		7.18.3.1 internal::Singleton < const Init >	190
7.19	qpp::ex	cception::InvalidIterator Class Reference	191
	7.19.1	Detailed Description	192
	7.19.2	Member Function Documentation	192
		7.19.2.1 type_description()	192
7.20	qpp::int	ternal::IOManipEigen Class Reference	192
	7.20.1	Constructor & Destructor Documentation	193
		7.20.1.1 IOManipEigen() [1/2]	193
		7.20.1.2 IOManipEigen() [2/2]	194
	7.20.2	Member Function Documentation	194
		7.20.2.1 display()	194
	7.20.3	Member Data Documentation	194
		7.20.3.1 A	194
		7.20.3.2 chop	194
7.21	qpp::int	ternal::IOManipPointer< PointerType > Class Template Reference	195
	7.21.1	Constructor & Destructor Documentation	196
		7.21.1.1 IOManipPointer() [1/2]	196
		7.21.1.2 IOManipPointer() [2/2]	196
	7.21.2	Member Function Documentation	196
		7.21.2.1 display()	196
		7.21.2.2 operator=()	197
	7.21.3	Member Data Documentation	197
		7.21.3.1 end	197
		7.21.3.2 N	197

CONTENTS xvii

7.21.3.3 p
7.21.3.4 separator
7.21.3.5 start
7.22 qpp::internal::IOManipRange< InputIterator > Class Template Reference
7.22.1 Constructor & Destructor Documentation
7.22.1.1 IOManipRange() [1/2]
7.22.1.2 IOManipRange() [2/2]
7.22.2 Member Function Documentation
7.22.2.1 display()
7.22.2.2 operator=()
7.22.3 Member Data Documentation
7.22.3.1 end
7.22.3.2 first
7.22.3.3 last
7.22.3.4 separator
7.22.3.5 start
7.23 qpp::is_complex< T > Struct Template Reference
7.23.1 Detailed Description
7.24 qpp::is_complex< std::complex< T >> Struct Template Reference
7.24.1 Detailed Description
7.25 qpp::is_iterable < T, typename > Struct Template Reference
7.25.1 Detailed Description
7.26 qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval< T >().end()), typename T::value_type >> Struct Template Reference
7.26.1 Detailed Description
7.27 qpp::is_matrix_expression < Derived > Struct Template Reference
7.27.1 Detailed Description
7.28 qpp::QCircuitDescription::iterator Class Reference
7.28.1 Detailed Description
7.28.2 Member Typedef Documentation
7.28.2.1 difference_type

xviii CONTENTS

		7.28.2.2 iterator_category	38
		7.28.2.3 pointer	38
		7.28.2.4 reference	38
		7.28.2.5 value_type	38
	7.28.3	Constructor & Destructor Documentation	38
		7.28.3.1 iterator() [1/2]	38
		7.28.3.2 iterator() [2/2])9
	7.28.4	Member Function Documentation)9
		7.28.4.1 operator"!=())9
		7.28.4.2 operator*())9
		7.28.4.3 operator++() [1/2])9
		7.28.4.4 operator++() [2/2]	10
		7.28.4.5 operator=()	10
		7.28.4.6 operator==()	10
		7.28.4.7 set_()	10
	7.28.5	Friends And Related Function Documentation	11
		7.28.5.1 QCircuit	11
	7.28.6	Member Data Documentation	11
		7.28.6.1 elem	11
		7.28.6.2 qcd	11
		7.28.6.3 QCircuitDescription	11
7.29	qpp::m	ke_void < Ts > Struct Template Reference	12
	7.29.1	Detailed Description	12
	7.29.2	Member Typedef Documentation	12
		7.29.2.1 type	12
7.30	qpp::ex	eption::MatrixMismatchSubsys Class Reference	13
	7.30.1	Detailed Description	14
	7.30.2	Member Function Documentation	14
		7.30.2.1 type_description()	14
7.31	qpp::ex	eption::MatrixNotCvector Class Reference	14

CONTENTS xix

	7.31.1	Detailed Description	216
	7.31.2	Member Function Documentation	216
		7.31.2.1 type_description()	216
7.32	qpp::ex	cception::MatrixNotRvector Class Reference	216
	7.32.1	Detailed Description	217
	7.32.2	Member Function Documentation	217
		7.32.2.1 type_description()	218
7.33	qpp::ex	cception::MatrixNotSquare Class Reference	218
	7.33.1	Detailed Description	219
	7.33.2	Member Function Documentation	219
		7.33.2.1 type_description()	220
7.34	qpp::ex	cception::MatrixNotSquareNorCvector Class Reference	220
	7.34.1	Detailed Description	221
	7.34.2	Member Function Documentation	221
		7.34.2.1 type_description()	222
7.35	qpp::ex	cception::MatrixNotSquareNorRvector Class Reference	222
	7.35.1	Detailed Description	223
	7.35.2	Member Function Documentation	223
		7.35.2.1 type_description()	224
7.36	qpp::ex	cception::MatrixNotSquareNorVector Class Reference	224
	7.36.1	Detailed Description	225
	7.36.2	Member Function Documentation	225
		7.36.2.1 type_description()	226
7.37	qpp::ex	cception::MatrixNotVector Class Reference	226
	7.37.1	Detailed Description	227
	7.37.2	Member Function Documentation	227
		7.37.2.1 type_description()	228
7.38	qpp::Q	CircuitDescription::MeasureStep Struct Reference	228
	7.38.1	Detailed Description	229
	7.38.2	Constructor & Destructor Documentation	229

CONTENTS

		7.38.2.1 MeasureStep() [1/2]	29
		7.38.2.2 MeasureStep() [2/2]	29
	7.38.3	Member Data Documentation	30
		7.38.3.1 c_reg	30
		7.38.3.2 mats	30
		7.38.3.3 measurement_type	30
		7.38.3.4 name	30
		7.38.3.5 step_no	30
		7.38.3.6 target	31
7.39	qpp::ex	xception::NoCodeword Class Reference	31
	7.39.1	Detailed Description	32
	7.39.2	Member Function Documentation	32
		7.39.2.1 type_description()	32
7.40	qpp::ex	xception::NotBipartite Class Reference	33
	7.40.1	Detailed Description	34
	7.40.2	Member Function Documentation	34
		7.40.2.1 type_description()	34
7.41	qpp::ex	xception::NotImplemented Class Reference	35
	7.41.1	Detailed Description	36
	7.41.2	Member Function Documentation	36
		7.41.2.1 type_description()	36
7.42	qpp::ex	xception::NotQubitCvector Class Reference	37
	7.42.1	Detailed Description	38
	7.42.2	Member Function Documentation	38
		7.42.2.1 type_description()	38
7.43	qpp::ex	xception::NotQubitMatrix Class Reference	38
	7.43.1	Detailed Description	10
	7.43.2	Member Function Documentation	10
		7.43.2.1 type_description()	10
7.44	qpp::ex	xception::NotQubitRvector Class Reference	10

CONTENTS xxi

	7.44.1	Detailed Description	241
	7.44.2	Member Function Documentation	241
		7.44.2.1 type_description()	242
7.45	qpp::ex	cception::NotQubitSubsys Class Reference	242
	7.45.1	Detailed Description	243
	7.45.2	Member Function Documentation	243
		7.45.2.1 type_description()	244
7.46	qpp::ex	cception::NotQubitVector Class Reference	244
	7.46.1	Detailed Description	245
	7.46.2	Member Function Documentation	245
		7.46.2.1 type_description()	246
7.47	qpp::ex	cception::OutOfRange Class Reference	246
	7.47.1	Detailed Description	247
	7.47.2	Member Function Documentation	247
		7.47.2.1 type_description()	247
7.48	qpp::ex	cception::PermInvalid Class Reference	248
	7.48.1	Detailed Description	249
	7.48.2	Member Function Documentation	249
		7.48.2.1 type_description()	249
7.49	qpp::ex	cception::PermMismatchDims Class Reference	250
	7.49.1	Detailed Description	251
	7.49.2	Member Function Documentation	251
		7.49.2.1 type_description()	252
7.50	qpp::Q	Circuit Class Reference	252
	7.50.1	Detailed Description	254
	7.50.2	Constructor & Destructor Documentation	254
		7.50.2.1 QCircuit() [1/2]	254
		7.50.2.2 QCircuit() [2/2]	255
	7.50.3	Member Function Documentation	255
		7.50.3.1 display()	255

xxii CONTENTS

		7.50.3.2 get_circuit_description()	55
		7.50.3.3 get_dit()	.56
		7.50.3.4 get_dits()	56
		7.50.3.5 get_ip()	56
		7.50.3.6 get_iter()	56
		7.50.3.7 get_m_ip()	.57
		7.50.3.8 get_measured() [1/2]	57
		7.50.3.9 get_measured() [2/2]	:57
		7.50.3.10 get_not_measured()	:57
		7.50.3.11 get_probs()	:58
		7.50.3.12 get_psi()	:58
		7.50.3.13 get_q_ip()	:58
		7.50.3.14 get_relative_pos_()	:58
		7.50.3.15 is_measurement_step()	:59
		7.50.3.16 reset()	:59
		7.50.3.17 run()	:59
		7.50.3.18 set_dit()	:59
		7.50.3.19 set_measured_()	60
	7.50.4	Member Data Documentation	60
		7.50.4.1 dits	60
		7.50.4.2 it	60
		7.50.4.3 probs	60
		7.50.4.4 psi	61
		7.50.4.5 qcd	61
		7.50.4.6 subsys	61
7.51	qpp::Q0	ircuitDescription Class Reference	61
	7.51.1	Detailed Description	:65
	7.51.2	Member Typedef Documentation	:65
		7.51.2.1 const_iterator	:65
	7.51.3	Member Enumeration Documentation	65

CONTENTS xxiii

	7.51.3.1	G	ateTy	φe.									 							265
	7.51.3.2	M	leasu	reTyp	oe							 	 					 	-	266
7.51.4	Construct	ctor	& De	struc	tor D)ocı	ume	enta	atio	n .		 	 					 		266
	7.51.4.1	G	Circu	itDes	script	ion	() .					 	 					 		267
7.51.5	Member I	Fu	nction	ı Doc	ume	ntat	tion					 	 					 		267
	7.51.5.1	_	to_JS	ON()								 	 					 		267
	7.51.5.2	b	egin()	[1/:	2] .							 	 							267
	7.51.5.3	b	egin()	[2/	2] .							 	 					 		268
	7.51.5.4	cl	begin	() .								 	 							268
	7.51.5.5	C	CTRL	.() [1	/4] .							 	 							268
	7.51.5.6	C	CTRL	.() [2	/4] .							 	 					 		269
	7.51.5.7	C	CTRL	. () [3	/4] .							 	 							269
	7.51.5.8	C	CTRL	.() [4	/4] .							 	 					 		269
	7.51.5.9	C	CTRL	_cus	tom() .						 	 							270
	7.51.5.10) c	end()									 	 							270
	7.51.5.11	1 C	TRL() [1/	4] .							 	 							271
	7.51.5.12	2 C	TRL() [2/	4] .							 	 							271
	7.51.5.13	3 C	TRL() [3/	4] .							 	 							272
	7.51.5.14	4 C	TRL() [4/	4] .							 	 					 		272
	7.51.5.15	5 C	TRL_	_custo	om()							 	 							273
	7.51.5.16	6 di	isplay	·() -								 	 					 		273
	7.51.5.17	7 e	nd() [[1/2]								 	 							274
	7.51.5.18	8 e	nd() [[2/2]								 	 							274
	7.51.5.19	9 g	ate()	[1/3]							 	 					 		274
	7.51.5.20	0 g	ate()	[2/3]							 	 					 		274
	7.51.5.21	1 g	ate()	[3/3]							 	 							275
	7.51.5.22	2 g	ate_c	ustor	n() .							 	 							275
	7.51.5.23	3 g	ate_fa	an() [[1/2]							 	 							276
	7.51.5.24	4 g	ate_fa	an() [[2/2]							 	 							276
	7.51.5.25	5 g	et_d())								 	 							277

xxiv CONTENTS

	7.51.5.26 get_gate_count()	•	2//
	7.51.5.27 get_gates()		277
	7.51.5.28 get_measured() [1/2]		277
	7.51.5.29 get_measured() [2/2]		278
	7.51.5.30 get_measurement_count()		278
	7.51.5.31 get_measurement_steps()		278
	7.51.5.32 get_measurements()		279
	7.51.5.33 get_name()		279
	7.51.5.34 get_nc()		279
	7.51.5.35 get_non_measured()		279
	7.51.5.36 get_nq()		280
	7.51.5.37 get_steps_count()		280
	7.51.5.38 measureV() [1/2]		280
	7.51.5.39 measureV() [2/2]		281
	7.51.5.40 measureZ()		281
	7.51.5.41 QFT()		281
	7.51.5.42 TFQ()		282
	7.51.5.43 to_JSON()		282
7.51.6	Friends And Related Function Documentation		282
	7.51.6.1 operator << [1/4]		282
	7.51.6.2 operator << [2/4]		283
	7.51.6.3 operator << [3/4]		283
	7.51.6.4 operator << [4/4]		284
7.51.7	Member Data Documentation		284
	7.51.7.1 d		284
	7.51.7.2 gates		284
	7.51.7.3 measured		284
	7.51.7.4 measurement_steps		285
	7.51.7.5 measurements		285
	7.51.7.6 name		285

CONTENTS xxv

		7.51.7.7 nc	35
		7.51.7.8 nq	35
		7.51.7.9 steps_cnt	35
7.52	qpp::ex	xception::QuditAlreadyMeasured Class Reference	36
	7.52.1	Detailed Description	37
	7.52.2	Member Function Documentation	37
		7.52.2.1 type_description()	37
7.53	qpp::Ra	andomDevices Class Reference	37
	7.53.1	Detailed Description	39
	7.53.2	Constructor & Destructor Documentation	39
		7.53.2.1 RandomDevices()	39
		7.53.2.2 ~RandomDevices()	39
	7.53.3	Member Function Documentation	39
		7.53.3.1 get_prng()	39
		7.53.3.2 load()	39
		7.53.3.3 save()	}0
	7.53.4	Friends And Related Function Documentation	}0
		7.53.4.1 internal::Singleton < RandomDevices >	}0
	7.53.5	Member Data Documentation	90
		7.53.5.1 prng	90
		7.53.5.2 rd) 1
7.54	qpp::in	ternal::Singleton< T > Class Template Reference)1
	7.54.1	Detailed Description)1
	7.54.2	Constructor & Destructor Documentation) 2
		7.54.2.1 Singleton() [1/2])2
		7.54.2.2 Singleton() [2/2]	92
		7.54.2.3 ~Singleton()	92
	7.54.3	Member Function Documentation	92
		7.54.3.1 get_instance()	93
		7.54.3.2 get_thread_local_instance()) 3

xxvi CONTENTS

	7.54.3.3 operator=()
7.55 qpp::e	xception::SizeMismatch Class Reference
7.55.1	Detailed Description
7.55.2	Member Function Documentation
	7.55.2.1 type_description()
7.56 qpp::S	States Class Reference
7.56.1	Detailed Description
7.56.2	Constructor & Destructor Documentation
	7.56.2.1 States()
	7.56.2.2 ~States()
7.56.3	Member Function Documentation
	7.56.3.1 jn()
	7.56.3.2 mes()
	7.56.3.3 minus()
	7.56.3.4 one()
	7.56.3.5 plus()
	7.56.3.6 zero()
7.56.4	Friends And Related Function Documentation
	7.56.4.1 internal::Singleton < const States >
7.56.5	Member Data Documentation
	7.56.5.1 b00
	7.56.5.2 b01
	7.56.5.3 b10
	7.56.5.4 b11
	7.56.5.5 GHZ
	7.56.5.6 pb00
	7.56.5.7 pb01
	7.56.5.8 pb10
	7.56.5.9 pb11
	7.56.5.10 pGHZ

CONTENTS xxvii

	7.56.5.11 pW	302
	7.56.5.12 px0	302
	7.56.5.13 px1	302
	7.56.5.14 py0	302
	7.56.5.15 py1	303
	7.56.5.16 pz0	303
	7.56.5.17 pz1	303
	7.56.5.18 W	303
	7.56.5.19 x0	303
	7.56.5.20 x1	303
	7.56.5.21 y0	304
	7.56.5.22 y1	304
	7.56.5.23 z0	304
	7.56.5.24 z1	304
7.57 qpp::ex	xception::SubsysMismatchDims Class Reference	305
7.57.1	Detailed Description	306
7.57.2	Member Function Documentation	306
	7.57.2.1 type_description()	306
7.58 qpp::T	imer< T, CLOCK_T > Class Template Reference	306
7.58.1	Detailed Description	308
7.58.2	Constructor & Destructor Documentation	308
	7.58.2.1 Timer() [1/3]	308
	7.58.2.2 Timer() [2/3]	308
	7.58.2.3 Timer() [3/3]	308
	7.58.2.4 ~Timer()	309
7.58.3	Member Function Documentation	309
	7.58.3.1 display()	309
	7.58.3.2 get_duration()	309
	7.58.3.3 operator=() [1/2]	310
	7.58.3.4 operator=() [2/2]	310

xxviii CONTENTS

		7.58.3.5 tic()
		7.58.3.6 tics()
		7.58.3.7 toc()
	7.58.4	Member Data Documentation
		7.58.4.1 end
		7.58.4.2 start
7.59	qpp::ex	ception::TypeMismatch Class Reference
	7.59.1	Detailed Description
	7.59.2	Member Function Documentation
		7.59.2.1 type_description()
7.60	qpp::ex	cception::UndefinedType Class Reference
	7.60.1	Detailed Description
	7.60.2	Member Function Documentation
		7.60.2.1 type_description()
7.61	qpp::ex	ception::Unknown Class Reference
	7.61.1	Detailed Description
	7.61.2	Member Function Documentation
		7.61.2.1 type_description()
7.62	qpp::Q0	CircuitDescription::iterator::value_type_ Struct Reference
	7.62.1	Constructor & Destructor Documentation
		7.62.1.1 value_type_() [1/2]
		7.62.1.2 value_type_() [2/2]
	7.62.2	Member Function Documentation
		7.62.2.1 display()
		7.62.2.2 operator=()
	7.62.3	Member Data Documentation
		7.62.3.1 ip
		7.62.3.2 is_measurement
		7.62.3.3 m_ip
		7.62.3.4 q_ip
		7.62.3.5 value_type_qcd
7.63	qpp::ex	ception::ZeroSize Class Reference
	7.63.1	Detailed Description
	7.63.2	Member Function Documentation
		7.63.2.1 type_description()

CONTENTS xxix

8	File I	Documentation	323
	8.1	classes/circuits.h File Reference	323
		8.1.1 Detailed Description	324
	8.2	classes/codes.h File Reference	324
		8.2.1 Detailed Description	324
	8.3	classes/exception.h File Reference	325
		8.3.1 Detailed Description	327
	8.4	classes/gates.h File Reference	327
		8.4.1 Detailed Description	327
	8.5	classes/idisplay.h File Reference	328
		8.5.1 Detailed Description	328
	8.6	classes/init.h File Reference	328
		8.6.1 Detailed Description	329
	8.7	classes/random_devices.h File Reference	329
		8.7.1 Detailed Description	329
	8.8	classes/reversible.h File Reference	330
		8.8.1 Detailed Description	330
	8.9	classes/states.h File Reference	330
		8.9.1 Detailed Description	331
	8.10	classes/timer.h File Reference	331
		8.10.1 Detailed Description	332
	8.11	constants.h File Reference	332
		8.11.1 Detailed Description	333
	8.12	entanglement.h File Reference	333
		8.12.1 Detailed Description	335
	8.13	entropies.h File Reference	335
		8.13.1 Detailed Description	336
	8.14	experimental/experimental.h File Reference	336
		8.14.1 Detailed Description	336
	8.15	functions.h File Reference	336

CONTENTS

	8.15.1 Detailed Description	340
8.16	input_output.h File Reference	341
	8.16.1 Detailed Description	342
8.17	instruments.h File Reference	342
	8.17.1 Detailed Description	343
8.18	internal/classes/iomanip.h File Reference	343
	8.18.1 Detailed Description	344
8.19	internal/classes/singleton.h File Reference	344
	8.19.1 Detailed Description	345
8.20	internal/util.h File Reference	345
	8.20.1 Detailed Description	346
8.21	MATLAB/matlab.h File Reference	347
	8.21.1 Detailed Description	347
8.22	number_theory.h File Reference	347
	8.22.1 Detailed Description	349
8.23	operations.h File Reference	349
	8.23.1 Detailed Description	351
8.24	qpp.h File Reference	351
	8.24.1 Detailed Description	353
	8.24.2 Macro Definition Documentation	353
	8.24.2.1 QPP_UNUSED	353
8.25	random.h File Reference	353
	8.25.1 Detailed Description	354
8.26	statistics.h File Reference	355
	8.26.1 Detailed Description	356
8.27	traits.h File Reference	356
	8.27.1 Detailed Description	357
8.28	types.h File Reference	357
	8.28.1 Detailed Description	358
8.29	/home/vlad/qpp/README.md File Reference	358

Index

359

Chapter 1

Quantum++

Version 1.1 - 26 November 2018

Build status:

Chat (questions/issues)

About

Quantum++ is a modern C++11 general purpose quantum computing library, composed solely of template header files. Quantum++ is written in standard C++11 and has very low external dependencies, using only the Eigen 3 linear algebra header-only template library and, if available, the OpenMP multi-processing library.

Quantum++ is not restricted to qubit systems or specific quantum information processing tasks, being capable of simulating arbitrary quantum processes. The main design factors taken in consideration were the ease of use, high portability, and high performance. The library's simulation capabilities are only restricted by the amount of available physical memory. On a typical machine (Intel i5 8Gb RAM) Quantum++ can successfully simulate the evolution of 25 qubits in a pure state or of 12 qubits in a mixed state reasonably fast.

To report any bugs or ask for additional features/enhancements, please submit an issue with an appropriate label.

If you are interesting in contributing to this project, feel free to contact me. Alternatively, create a custom branch, add your contribution, then finally create a pull request. If I accept the pull request, I will merge your custom branch with the latest development branch. The latter will eventually be merged into a future release version. To contribute, you need to have a solid knowledge of C++ (preferably C++11), including templates and the standard library, a basic knowledge of quantum computing and linear algebra, and working experience with Eigen 3.

For additional Eigen 3 documentation see http://eigen.tuxfamily.org/dox/. For a simple Eigen 3 quick ASCII reference see http://eigen.tuxfamily.org/dox/AsciiQuickReference.txt.

Copyright (c) 2013 - 2019 Vlad Gheorghiu, vgheorgh AT gmail DOT com.

License

Quantum++ is distributed under the MIT license. Please see the LICENSE file for more details.

Installation instructions and further documentation

Please see the installation guide https://github.com/vsoftco/qpp/blob/master/INSTALL.md "'INSTALL.md'" and the comprehensive Wiki for further documentation and detailed examples.

The official API documentation is available in PDF and HTML formats in the ${\tt doc}$ folder.

2 Quantum++

Chapter 2

Namespace Index

2.1 Namespace List

Here is a list of all namespaces with brief descriptions:

qpp
Quantum++ main namespace
qpp::exception
Quantum++ exception hierarchy namespace
qpp::experimental
Experimental/test functions/classes, do not use or modify
qpp::internal
Internal utility functions, do not use them directly or modify them
qpp::literals

4 Namespace Index

Chapter 3

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

qpp::internal::Display_Impl
qpp::internal::IOManipEigen
std::exception
qpp::exception::Exception
qpp::exception::CustomException
qpp::exception::DimsInvalid
qpp::exception::DimsMismatchCvector
qpp::exception::DimsMismatchMatrix
qpp::exception::DimsMismatchRvector
qpp::exception::DimsMismatchVector
app::exception::DimsNotEqual
qpp::exception::Duplicates
qpp::exception::InvalidIterator
qpp::exception::MatrixMismatchSubsys
qpp::exception::MatrixNotCvector
qpp::exception::MatrixNotRvector
qpp::exception::MatrixNotSquare
qpp::exception::MatrixNotSquareNorCvector
qpp::exception::MatrixNotSquareNorRvector
qpp::exception::MatrixNotSquareNorVector
qpp::exception::MatrixNotVector
qpp::exception::NoCodeword
qpp::exception::NotBipartite
qpp::exception::NotImplemented
qpp::exception::NotQubitCvector
qpp::exception::NotQubitMatrix
qpp::exception::NotQubitRvector
qpp::exception::NotQubitSubsys
qpp::exception::NotQubitVector
qpp::exception::OutOfRange
qpp::exception::PermInvalid
qpp::exception::PermMismatchDims
qpp::exception::QuditAlreadyMeasured
qpp::exception::SizeMismatch
app::exception::SubsysMismatchDims

6 Hierarchical Index

qpp::exception::TypeMismatch	2
qpp::exception::UndefinedType	3
qpp::exception::Unknown	5
qpp::exception::ZeroSize	0
false_type	
qpp::is_complex< T >	
qpp::is_iterable < T, typename >	
qpp::Bit_circuit::Gate_count	
qpp::QCircuitDescription::GateStep	
qpp::IDisplay	6
qpp::Dynamic_bitset	3
qpp::Bit_circuit	9
qpp::internal::IOManipEigen	2
qpp::internal::IOManipPointer< PointerType >	
qpp::internal::IOManipRange< InputIterator >	
qpp::QCircuit	
qpp::QCircuitDescription	
qpp::QCircuitDescription::iterator::value_type	
qpp::Timer< T, CLOCK_T >	ô
is_base_of	
qpp::is_matrix_expression< Derived >	
qpp::QCircuitDescription::iterator	
qpp::make_void < Ts >	
qpp::QCircuitDescription::MeasureStep	
qpp::internal::Singleton< T >	
qpp::internal::Singleton < const Codes >	
qpp::Codes	
qpp::internal::Singleton < const Gates >	1
qpp::Gates	0
qpp::internal::Singleton < const Init >	1
qpp::Init	9
qpp::internal::Singleton < const States >	
qpp::States	
qpp::internal::Singleton < RandomDevices >	
qpp::RandomDevices	
true type	•
qpp::is complex< std::complex< T >>	2
qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval< T	_
>().end()), typename T::value_type >>	4
· v v v	

Chapter 4

Class Index

4.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

qpp::Bit_circuit	
Classical reversible circuit simulator	129
qpp::Codes	
Const Singleton class that defines quantum error correcting codes	134
qpp::exception::CustomException	
Custom exception	137
qpp::exception::DimsInvalid	
Invalid dimension(s) exception	140
qpp::exception::DimsMismatchCvector	
Dimension(s) mismatch column vector size exception	141
qpp::exception::DimsMismatchMatrix	
Dimension(s) mismatch matrix size exception	143
qpp::exception::DimsMismatchRvector	
Dimension(s) mismatch row vector size exception	145
qpp::exception::DimsMismatchVector	
Dimension(s) mismatch vector size exception	147
qpp::exception::DimsNotEqual	
Dimensions not equal exception	149
qpp::internal::Display_Impl	151
qpp::exception::Duplicates	
System (e.g. std::vector) has duplicates exception	152
qpp::Dynamic_bitset	
Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std←	
::bitset <n>)</n>	153
qpp::exception::Exception	
Base class for generating Quantum++ custom exceptions	165
qpp::Bit_circuit::Gate_count	168
qpp::Gates	
Const Singleton class that implements most commonly used gates	170
qpp::QCircuitDescription::GateStep	
One step consisting only of gates/operators in the circuit	183
qpp::IDisplay	
Abstract class (interface) that mandates the definition of virtual std::ostream& display(std←	
::ostream& os) const	186
qpp::Init	
Const Singleton class that performs additional initializations/cleanups	189

8 Class Index

qpp::exception::InvalidIterator	
Invalid iterator	191
qpp::internal::IOManipEigen	192
qpp::internal::IOManipPointer< PointerType >	195
qpp::internal::IOManipRange< InputIterator >	198
qpp::is_complex< T >	
Checks whether the type is a complex type	201
qpp::is_complex < std::complex < T > > Checks whether the type is a complex number type, specialization for complex types	202
qpp::is_iterable< T, typename >	202
Checks whether <i>T</i> is compatible with an STL-like iterable container	203
<pre>qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval< T >().end()),</pre>	
Checks whether T is compatible with an STL-like iterable container, specialization for STL-like	
iterable containers	204
qpp::is_matrix_expression< Derived >	
Checks whether the type is an Eigen matrix expression	205
qpp::QCircuitDescription::iterator Quantum circuit description bound-checking (safe) iterator	206
qpp::make_void< Ts >	
Helper for qpp::to_void<> alias template	212
qpp::exception::MatrixMismatchSubsys	
Matrix mismatch subsystems exception	213
qpp::exception::MatrixNotCvector	
Matrix is not a column vector exception	214
qpp::exception::MatrixNotRvector	
Matrix is not a row vector exception	216
qpp::exception::MatrixNotSquare	
Matrix is not square exception	218
qpp::exception::MatrixNotSquareNorCvector	
Matrix is not square nor column vector exception	220
qpp::exception::MatrixNotSquareNorRvector	
Matrix is not square nor row vector exception	222
qpp::exception::MatrixNotSquareNorVector	
Matrix is not square nor vector exception	224
qpp::exception::MatrixNotVector	
Matrix is not a vector exception	226
qpp::QCircuitDescription::MeasureStep	
1 5 7	228
qpp::exception::NoCodeword	
•	231
qpp::exception::NotBipartite	
Not bi-partite exception	233
qpp::exception::NotImplemented	
Code not yet implemented	235
qpp::exception::NotQubitCvector Column vector is not 2 x 1 exception	237
qpp::exception::NotQubitMatrix	
Matrix is not 2 x 2 exception	238
qpp::exception::NotQubitRvector	
Row vector is not 1 x 2 exception	240
qpp::exception::NotQubitSubsys	
Subsystems are not qubits exception	242
qpp::exception::NotQubitVector	
Vector is not 2 x 1 nor 1 x 2 exception	244
qpp::exception::OutOfRange	
Argument out of range exception	246

4.1 Class List

qpp::exception::PermInvalid	
Invalid permutation exception	248
qpp::exception::PermMismatchDims	
Permutation mismatch dimensions exception	250
qpp::QCircuit	
Quantum circuit simulator class	252
qpp::QCircuitDescription	
Quantum circuit description class	261
qpp::exception::QuditAlreadyMeasured	
Qudit was already measured exception	286
qpp::RandomDevices	
Singleton class that manages the source of randomness in the library	287
qpp::internal::Singleton< T >	
Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously	
recurring template pattern)	291
qpp::exception::SizeMismatch	
Size mismatch exception	293
qpp::States	
Const Singleton class that implements most commonly used states	295
qpp::exception::SubsysMismatchDims	
Subsystems mismatch dimensions exception	305
qpp::Timer< T, CLOCK_T >	
Chronometer	306
qpp::exception::TypeMismatch	
Type mismatch exception	312
qpp::exception::UndefinedType	
Not defined for this type exception	313
qpp::exception::Unknown	
Unknown exception	315
qpp::QCircuitDescription::iterator::value_type	317
qpp::exception::ZeroSize	
Object has zero size exception	320

10 Class Index

Chapter 5

File Index

5.1 File List

Here is a list of all files with brief descriptions:

constants.h
Constants
entanglement.h
Entanglement functions
entropies.h
Entropy functions
functions.h
Generic quantum computing functions
input_output.h
Input/output functions
instruments.h
Measurement functions
number_theory.h
Number theory functions
operations.h
Quantum operation functions
qpp.h
Quantum++ main header file, includes all other necessary headers
random.h
Randomness-related functions
statistics.h
Statistics functions
traits.h
Type traits
types.h
Type aliases
classes/circuits.h
Support for qudit quantum circuits
classes/codes.h
Quantum error correcting codes
classes/exception.h
Exceptions
classes/gates.h
Quantum gates
classes/idisplay.h
Display interface via the non-virtual interface (NVI)

12 File Index

sses/init.h	
Initialization	28
sses/random_devices.h	
Random devices	29
sses/reversible.h	
Support for classical reversible circuits	30
sses/states.h	
Quantum states	30
sses/timer.h	
Timing	31
perimental/experimental.h	
Experimental/test functions/classes	36
ernal/util.h	
Internal utility functions	15
ernal/classes/iomanip.h	
Input/output manipulators	13
ernal/classes/singleton.h	
Singleton pattern via CRTP	14
ATLAB/matlab.h	
Input/output interfacing with MATLAB	17

Chapter 6

Namespace Documentation

6.1 qpp Namespace Reference

Quantum++ main namespace.

Namespaces

· exception

Quantum++ exception hierarchy namespace.

· experimental

Experimental/test functions/classes, do not use or modify.

internal

Internal utility functions, do not use them directly or modify them.

literals

Classes

· class Bit_circuit

Classical reversible circuit simulator.

• class Codes

const Singleton class that defines quantum error correcting codes

· class Dynamic_bitset

 $\textit{Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset < N >) \\$

· class Gates

const Singleton class that implements most commonly used gates

class IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

class Init

const Singleton class that performs additional initializations/cleanups

struct is_complex

Checks whether the type is a complex type.

struct is complex< std::complex< T >>

Checks whether the type is a complex number type, specialization for complex types.

struct is_iterable

Checks whether T is compatible with an STL-like iterable container.

struct is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval< T >().end()), typename T::value_type >>

Checks whether T is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

struct is_matrix_expression

Checks whether the type is an Eigen matrix expression.

· struct make void

Helper for qpp::to_void<> alias template.

· class QCircuit

Quantum circuit simulator class.

· class QCircuitDescription

Quantum circuit description class.

· class RandomDevices

Singleton class that manages the source of randomness in the library.

· class States

const Singleton class that implements most commonly used states

· class Timer

Chronometer.

Typedefs

```
    template<typename... Ts>
        using to_void = typename make_void< Ts... >::type
```

Alias template that implements the proposal for void_t.

• using idx = std::size_t

Non-negative integer index, make sure you use an unsigned type.

• using bigint = long long int

Big integer.

• using cplx = std::complex < double >

Complex number in double precision.

• using ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector.

• using bra = Eigen::RowVectorXcd

Complex (double precision) dynamic Eigen row vector.

• using cmat = Eigen::MatrixXcd

Complex (double precision) dynamic Eigen matrix.

• using dmat = Eigen::MatrixXd

Real (double precision) dynamic Eigen matrix.

 $\bullet \ \ \text{template}{<} \text{typename Scalar} >$

```
using dyn_mat = Eigen::Matrix < Scalar, Eigen::Dynamic, Eigen::Dynamic >
```

Dynamic Eigen matrix over the field specified by Scalar.

template<typename Scalar >

```
using dyn_col_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 >
```

Dynamic Eigen column vector over the field specified by Scalar.

template<typename Scalar >

```
using dyn_row_vect = Eigen::Matrix < Scalar, 1, Eigen::Dynamic >
```

Dynamic Eigen row vector over the field specified by Scalar.

Functions

```
    constexpr cplx operator"" _i (long double x) noexcept

      User-defined literal for complex i = \sqrt{-1} (real overload)

    cplx omega (idx D)

      D-th root of unity.
• template<typename Derived >
  dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx >
  &dims)
     Schmidt coefficients of the bi-partite pure state A.
• template<typename Derived >
  dyn_col_vect< double > schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  cmat schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat schmidtA (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Bob side.

    template<typename Derived >

  cmat schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Bob side.

    template<typename Derived >

  std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx >
  &dims)
      Schmidt probabilities of the bi-partite pure state A.

    template<typename Derived >

  std::vector< double > schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt probabilities of the bi-partite pure state A.

    template<typename Derived >

  \label{lem:double entanglement} \mbox{double entanglement (const Eigen::MatrixBase< Derived > \&A, const std::vector< idx > \&dims)}
      Entanglement of the bi-partite pure state A.
• template<typename Derived >
  double entanglement (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Entanglement of the bi-partite pure state A.
• template<typename Derived >
  double gconcurrence (const Eigen::MatrixBase< Derived > &A)
      G-concurrence of the bi-partite pure state A.

    template<typename Derived >

  double negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Negativity of the bi-partite mixed state A.

    template<typename Derived >

  double negativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
     Negativity of the bi-partite mixed state A.

    template<typename Derived >

  double lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
     Logarithmic negativity of the bi-partite mixed state A.
ullet template<typename Derived >
  double lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Logarithmic negativity of the bi-partite mixed state A.
```

```
• template<typename Derived >
  double concurrence (const Eigen::MatrixBase< Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.

    template<typename Derived >

  double entropy (const Eigen::MatrixBase< Derived > &A)
      von-Neumann entropy of the density matrix A

    double entropy (const std::vector< double > &prob)

     Shannon entropy of the probability distribution prob.

    template<typename Derived >

  double renyi (const Eigen::MatrixBase< Derived > &A, double alpha)
     Renyi- \alpha entropy of the density matrix A, for \alpha \geq 0.

    double renyi (const std::vector< double > &prob, double alpha)

     Renyi- \alpha entropy of the probability distribution prob, for \alpha > 0.
• template<typename Derived >
  double tsallis (const Eigen::MatrixBase< Derived > &A, double q)
      Tsallis- q entropy of the density matrix A, for q \geq 0.

    double tsallis (const std::vector< double > &prob, double q)

      Tsallis- q entropy of the probability distribution prob, for q \geq 0.
• template<typename Derived >
  double qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx > &subsysB, const std::vector< idx > &dims)
     Quantum mutual information between 2 subsystems of a composite system.

    template<typename Derived >

  double qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const
  std::vector< idx > &subsysB, idx d=2)
      Quantum mutual information between 2 subsystems of a composite system.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > transpose (const Eigen::MatrixBase< Derived > &A)
      Transpose.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > adjoint (const Eigen::MatrixBase< Derived > &A)
     Adioint.
• template<typename Derived >
  dyn mat< typename Derived::Scalar > inverse (const Eigen::MatrixBase< Derived > &A)
     Inverse.

    template<typename Derived >

  Derived::Scalar trace (const Eigen::MatrixBase< Derived > &A)
      Trace.

    template<typename Derived >

  Derived::Scalar det (const Eigen::MatrixBase < Derived > &A)
      Determinant.
• template<typename Derived >
  Derived::Scalar logdet (const Eigen::MatrixBase< Derived > &A)
     Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar sum (const Eigen::MatrixBase< Derived > &A)
     Element-wise sum of A.

    template<typename Derived >

  Derived::Scalar prod (const Eigen::MatrixBase < Derived > &A)
```

Element-wise product of A.

```
• template<typename Derived >
  double norm (const Eigen::MatrixBase< Derived > &A)
      Frobenius norm.

    template<typename Derived >

  std::pair< dyn_col_vect< cplx >, cmat > eig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition.

    template<typename Derived >

  \label{eq:const_equal} \mbox{dyn\_col\_vect} < \mbox{cplx} > \mbox{evals} \mbox{ (const Eigen::MatrixBase} < \mbox{Derived} > \&\mbox{A})
      Eigenvalues.

    template<typename Derived >

  cmat evects (const Eigen::MatrixBase< Derived > &A)
      Eigenvectors.

    template<typename Derived >

  std::pair< dyn col vect< double >, cmat > heig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition of Hermitian expression.
• template<typename Derived >
  dyn_col_vect< double > hevals (const Eigen::MatrixBase< Derived > &A)
     Hermitian eigenvalues.

    template<typename Derived >

  cmat hevects (const Eigen::MatrixBase< Derived > &A)
      Eigenvectors of Hermitian matrix.

    template<typename Derived >

  std::tuple< cmat, dyn_col_vect< double >, cmat > svd (const Eigen::MatrixBase< Derived > &A)
      Full singular value decomposition.

    template<typename Derived >

  dyn_col_vect< double > svals (const Eigen::MatrixBase< Derived > &A)
      Singular values.
• template<typename Derived >
  cmat svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.

    template<typename Derived >

  cmat svdV (const Eigen::MatrixBase< Derived > &A)
      Right singular vectors.

    template<typename Derived >

  cmat funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
      Functional calculus f(A)

    template<typename Derived >

  cmat sqrtm (const Eigen::MatrixBase< Derived > &A)
      Matrix square root.

    template<typename Derived >

  cmat absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.
• template<typename Derived >
  cmat expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.

    template<typename Derived >

  cmat logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.

    template<typename Derived >

  cmat sinm (const Eigen::MatrixBase< Derived > &A)
     Matrix sin.

    template<typename Derived >

  cmat cosm (const Eigen::MatrixBase< Derived > &A)
```

Matrix cos. • template<typename Derived > cmat spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z) Matrix power. • template<typename Derived > dyn_mat< typename Derived::Scalar > powm (const Eigen::MatrixBase< Derived > &A, idx n) Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm. template<typename Derived > double schatten (const Eigen::MatrixBase< Derived > &A, double p) Schatten matrix norm. • template<typename OutputScalar , typename Derived > dyn mat< OutputScalar > cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const typename Derived::Scalar &)) Functor. template<typename T > dyn_mat< typename T::Scalar > kron (const T &head) Kronecker product. template<typename T, typename... Args> dyn mat< typename T::Scalar > kron (const T &head, const Args &... tail) Kronecker product. template<typename Derived > dyn_mat< typename Derived::Scalar > kron (const std::vector< Derived > &As) Kronecker product. template<typename Derived > dyn mat< typename Derived::Scalar > kron (const std::initializer list< Derived > &As) Kronecker product. • template<typename Derived > dyn_mat< typename Derived::Scalar > kronpow (const Eigen::MatrixBase< Derived > &A, idx n) Kronecker power. template<typename T > dyn_mat< typename T::Scalar > dirsum (const T &head) Direct sum. • template<typename T , typename... Args> dyn_mat< typename T::Scalar > dirsum (const T &head, const Args &... tail) Direct sum. template<typename Derived > dyn_mat< typename Derived::Scalar > dirsum (const std::vector< Derived > &As) Direct sum. • template<typename Derived > dyn_mat< typename Derived::Scalar > dirsum (const std::initializer_list< Derived > &As)

Direct sum.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)

Direct sum power.

• template<typename Derived >

dyn mat< typename Derived::Scalar > reshape (const Eigen::MatrixBase< Derived > &A, idx rows, idx cols)

Reshape.

template<typename Derived1 , typename Derived2 >

dyn mat< typename Derived1::Scalar > comm (const Eigen::MatrixBase< Derived1 > &A, const Eigen::← MatrixBase < Derived2 > &B)

Commutator.

19 template<typename Derived1 , typename Derived2 > dyn_mat< typename Derived1::Scalar > anticomm (const Eigen::MatrixBase< Derived1 > &A, const Eigen::MatrixBase< Derived2 > &B) Anti-commutator. template<typename Derived > dyn_mat< typename Derived::Scalar > prj (const Eigen::MatrixBase< Derived > &A) Projector. template<typename Derived > dyn mat< typename Derived::Scalar > grams (const std::vector< Derived > &As) Gram-Schmidt orthogonalization. template<typename Derived > dyn_mat< typename Derived::Scalar > grams (const std::initializer_list< Derived > &As) Gram-Schmidt orthogonalization. • template<typename Derived > dyn_mat< typename Derived::Scalar > grams (const Eigen::MatrixBase< Derived > &A) Gram-Schmidt orthogonalization. std::vector< idx > n2multiidx (idx n, const std::vector< idx > &dims) Non-negative integer index to multi-index. idx multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims) Multi-index to non-negative integer index. ket mket (const std::vector < idx > &mask, const std::vector < idx > &dims) Multi-partite qudit ket. ket mket (const std::vector < idx > &mask, idx d=2) Multi-partite qudit ket. cmat mprj (const std::vector < idx > &mask, const std::vector < idx > &dims) Projector onto multi-partite qudit ket. cmat mprj (const std::vector < idx > &mask, idx d=2) Projector onto multi-partite qudit ket. • template<typename InputIterator > std::vector< double > abssq (InputIterator first, InputIterator last) Computes the absolute values squared of an STL-like range of complex numbers. template<typename Container > std::vector< double > abssq (const Container &c, typename std::enable if< is iterable< Container >::value >::type *=nullptr) Computes the absolute values squared of an STL-like container. template<typename Derived > std::vector< double > abssq (const Eigen::MatrixBase< Derived > &A) Computes the absolute values squared of an Eigen expression. template<typename InputIterator > std::iterator_traits< InputIterator >::value_type sum (InputIterator first, InputIterator last) Element-wise sum of an STL-like range. • template<typename Container > Container::value_type sum (const Container &c, typename std::enable_if< is_iterable< Container >::value

>::type *=nullptr)

Element-wise sum of the elements of an STL-like container.

template<typename InputIterator >

std::iterator traits< InputIterator >::value type prod (InputIterator first, InputIterator last)

Element-wise product of an STL-like range.

template<typename Container >

Container::value_type prod (const Container &c, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Element-wise product of the elements of an STL-like container.

• template<typename Derived >

dyn_col_vect< typename Derived::Scalar > rho2pure (const Eigen::MatrixBase< Derived > &A)

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

template<typename T >

std::vector< T > complement (std::vector< T > subsys, idx N)

Constructs the complement of a subsystem vector.

• template<typename Derived >

std::vector< double > rho2bloch (const Eigen::MatrixBase< Derived > &A)

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

cmat bloch2rho (const std::vector< double > &r)

Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.

• template<typename Derived >

internal::IOManipEigen disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)

Eigen expression ostream manipulator.

• internal::IOManipEigen disp (cplx z, double chop=qpp::chop)

Complex number ostream manipulator.

• template<typename InputIterator >

internal::IOManipRange < InputIterator > disp (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")

Range ostream manipulator.

• template<typename Container >

internal::IOManipRange< typename Container::const_iterator > disp (const Container &c, const std::string &separator, const std::string &start="[", const std::string &end="]", typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

template<typename PointerType >

internal::IOManipPointer< PointerType > disp (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")

C-style pointer ostream manipulator.

• template<typename Derived >

void save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

• template<typename Derived >

dyn mat< typename Derived::Scalar > load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)

Generalized inner product.

template<typename Derived >

dyn_col_vect< typename Derived::Scalar > ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::← MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2)

Generalized inner product.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple < idx, std::vector < double >, std::vector < cmat > > measure (const Eigen::MatrixBase < Derived > &A, const std::initializer_list < cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const std::initializer list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

ullet template<typename Derived >

std::tuple< std::vector< idx >, double, cmat > measure_seq (const Eigen::MatrixBase< Derived > &A, std::vector< idx > target, idx d=2)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

• template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< cplx > >::type loadM ← ATLAB (const std::string &mat_file, const std::string &var_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::

Scalar > >::type loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

• std::vector< int > x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

double contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

bigint gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

bigint lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > invperm (const std::vector< idx > &perm)

Inverse permutation.

• std::vector< idx > compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

std::vector< bigint > factors (bigint a)

Prime factor decomposition.

bigint modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

• bigint modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

std::tuple < bigint, bigint, bigint > egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

• bigint modiny (bigint a, bigint p)

Modular inverse of a mod p.

• bool isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

bigint randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

• std::vector< std::pair< int, int > > convergents (const std::vector< int > &cf)

Convergents.

• std::vector< std::pair< int, int > > convergents (double x, idx N)

Convergents.

template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, const
std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

- template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > applyCTRL (const Eigen::MatrixBase< Derived1 > &state, const
Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target, idx
d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen ← ::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

template < typename Derived >
 cmat apply (const Eigen::MatrixBase < Derived > &A, const std::vector < cmat > &Ks)

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

template<typename Derived >

 $\begin{array}{l} \textbf{cmat apply} \ (\textbf{const Eigen::} \textbf{MatrixBase} < \textbf{Derived} > \& \textbf{A}, \ \textbf{const std::} \textbf{vector} < \textbf{cmat} > \& \textbf{Ks}, \ \textbf{const std::} \textbf{vector} < \textbf{idx} \\ > \& \textbf{target}, \ \textbf{const std::} \textbf{vector} < \textbf{idx} > \& \textbf{dims}) \end{array}$

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

template<typename Derived >

cmat apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx
> &target, idx d=2)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat kraus2super (const std::vector< cmat > &Ks)

Superoperator matrix.

cmat kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector < cmat > choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace1 (const Eigen::MatrixBase< Derived > &A, const std↔ ::vector< idx > &dims)

Partial trace.

• template<typename Derived >

 $\label{localization} \mbox{dyn_mat} < \mbox{typename Derived::Scalar} > \mbox{ptrace1} \mbox{ (const Eigen::MatrixBase} < \mbox{Derived} > \&\mbox{A, idx d=2)}$

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &dims)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector<
idx > &target, const std::vector< idx > &dims)

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > ptrace (const Eigen::MatrixBase< Derived > &A, const std::vector
idx > &target, idx d=2)

Partial trace.

template<typename Derived >

dyn_mat< typename Derived::Scalar > ptranspose (const Eigen::MatrixBase< Derived > &A, const std
::vector< idx > &target, const std::vector< idx > &dims)

Partial transpose.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > ptranspose (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)

Partial transpose.

template<typename Derived >

Subsystem permutation.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > syspermute (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &perm, idx d=2)

Subsystem permutation.

template<typename Derived >

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

template<typename Derived >

dyn_mat< typename Derived::Scalar > applyTFQ (const Eigen::MatrixBase< Derived > &A, const std↔ ::vector< idx > &target, idx d=2, bool swap=true)

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

dyn_col_vect< typename Derived::Scalar > TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

• template<typename Derived >

dyn_col_vect< typename Derived::Scalar > QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Qudit quantum Fourier transform.

double rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

• bigint rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx randidx (idx a=std::numeric_limits< idx >::min(), idx b=std::numeric_limits< idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

• template<typename Derived >

Derived rand (idx rows, idx cols, double a=0, double b=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

template<>

dmat rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

template<>

cmat rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived randn (idx rows, idx cols, double mean=0, double sigma=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

template<>

dmat randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

template<>

cmat randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

double randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

• cmat randU (idx D=2)

Generates a random unitary matrix.

cmat randV (idx Din, idx Dout)

Generates a random isometry matrix.

std::vector< cmat > randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat randH (idx D=2)

Generates a random Hermitian matrix.

ket randket (idx D=2)

Generates a random normalized ket (pure state vector)

cmat randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.

std::vector< double > uniform (idx N)

Uniform probability distribution vector.

std::vector< double > marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > marginalY (const dmat &probXY)

Marginal distribution.

template<typename Container >

double avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_iterable<
Container >::value >::type *=nullptr)

Average.

• template<typename Container >

double cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_ iterable< Container >::value >::type *=nullptr)

Covariance.

• template<typename Container >

 $\label{lem:const} \begin{tabular}{ll} double & var (const std::vector < double > & prob, const Container & X, typename std::enable_if < is_iterable < Container >::value >::type *=nullptr) \end{tabular}$

Variance.

template<typename Container >

double sigma (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_← iterable< Container >::value >::type *=nullptr)

Standard deviation.

• template<typename Container >

double cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_← iterable< Container >::value >::type *=nullptr)

Correlation.

Variables

• constexpr double chop = 1e-10

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

• constexpr double eps = 1e-12

Used to decide whether a number or expression in double precision is zero or not.

constexpr idx maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

constexpr double pi = 3.141592653589793238462643383279502884

7

- constexpr double ee = 2.718281828459045235360287471352662497
 Base of natural logarithm, e.
- constexpr double infty = std::numeric_limits<double>::max()
 Used to denote infinity in double precision.
- const idx idx_infty = static_cast<idx>(-1)

Used to denote the largest unsigned index.

6.1.1 Detailed Description

Quantum++ main namespace.

6.1.2 Typedef Documentation

6.1.2.1 bigint

```
using qpp::bigint = typedef long long int
```

Big integer.

6.1.2.2 bra

```
using qpp::bra = typedef Eigen::RowVectorXcd
```

Complex (double precision) dynamic Eigen row vector.

6.1.2.3 cmat

```
using qpp::cmat = typedef Eigen::MatrixXcd
```

Complex (double precision) dynamic Eigen matrix.

6.1.2.4 cplx

```
using qpp::cplx = typedef std::complex<double>
```

Complex number in double precision.

```
6.1.2.5 dmat
```

```
using qpp::dmat = typedef Eigen::MatrixXd
```

Real (double precision) dynamic Eigen matrix.

6.1.2.6 dyn_col_vect

```
template<typename Scalar >
using qpp::dyn_col_vect = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, 1>
```

Dynamic Eigen column vector over the field specified by Scalar.

Example:

```
// type of colvect is Eigen::Matrix<float, Eigen::Dynamic, 1>
dyn_col_vect<float> colvect(2);
```

6.1.2.7 dyn_mat

```
template<typename Scalar >
using qpp::dyn_mat = typedef Eigen::Matrix<Scalar, Eigen::Dynamic, Eigen::Dynamic>
```

Dynamic Eigen matrix over the field specified by Scalar.

Example:

```
// type of mat is Eigen::Matrix<float, Eigen::Dynamic, Eigen::Dynamic>
dyn_mat<float> mat(2, 3);
```

6.1.2.8 dyn_row_vect

```
template<typename Scalar >
using qpp::dyn_row_vect = typedef Eigen::Matrix<Scalar, 1, Eigen::Dynamic>
```

Dynamic Eigen row vector over the field specified by Scalar.

Example:

```
// type of rowvect is Eigen::Matrix<float, 1, Eigen::Dynamic>
dyn_row_vect<float> rowvect(3);
```

6.1.2.9 idx

```
using qpp::idx = typedef std::size_t
```

Non-negative integer index, make sure you use an unsigned type.

6.1.2.10 ket

```
using qpp::ket = typedef Eigen::VectorXcd
```

Complex (double precision) dynamic Eigen column vector.

6.1.2.11 to_void

```
template<typename... Ts>
using qpp::to_void = typedef typename make_void<Ts...>::type
```

Alias template that implements the proposal for void t.

See also


```
http://www.open-std.org/jtc1/sc22/wg21/docs/papers/2014/n3911
```

6.1.3 Function Documentation

6.1.3.1 absm()

Matrix absolute value.

Parameters



Returns

Matrix absolute value of A

Computes the absolute values squared of an STL-like range of complex numbers.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Real vector consisting of the range absolute values squared

6.1.3.3 abssq() [2/3]

Computes the absolute values squared of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Real vector consisting of the container's absolute values squared

6.1.3.4 abssq() [3/3]

Computes the absolute values squared of an Eigen expression.

Parameters

```
A Eigen expression
```

Returns

Real vector consisting of the absolute values squared

6.1.3.5 adjoint()

Adjoint.

Parameters

```
A Eigen expression
```

Returns

Adjoint (Hermitian conjugate) of A, as a dynamic matrix over the same scalar field as A

6.1.3.6 anticomm()

Anti-commutator.

See also

qpp::comm()

Anti-commutator $\{A,B\} = AB + BA$. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
В	Eigen expression

Returns

Anti-commutator AB+BA, as a dynamic matrix over the same scalar field as \emph{A}

```
6.1.3.7 apply() [1/5]
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
dims	Dimensions of the multi-partite system

Returns

Gate A applied to the part target of state

```
6.1.3.8 apply() [2/5]
```

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression
Α	Eigen expression
target	Subsystem indexes where the gate A is applied
d	Subsystem dimensions

Returns

Gate A applied to the part target of state

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*.

Parameters

Α	Eigen expression	
Ks	Set of Kraus operators	
target	Subsystem indexes where the Kraus operators Ks are applied	
dims	Dimensions of the multi-partite system	

Returns

Output density matrix after the action of the channel

Applies the channel specified by the set of Kraus operators *Ks* to the part *target* of the multi-partite density matrix *A*.

Parameters

Α	Eigen expression	
Ks	Set of Kraus operators	
target	Subsystem indexes where the Kraus operators Ks are applied	
d	Subsystem dimensions	

Returns

Output density matrix after the action of the channel

6.1.3.12 applyCTRL() [1/2]

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate *A* must match the dimension of *target*. Also, all control subsystems in *ctrl* must have the same dimension.

Parameters

state	Eigen expression	
Α	Eigen expression	
ctrl	Control subsystem indexes	
target	get Subsystem indexes where the gate A is applied	
எனிச்சுக்க by Diagensions of the multi-partite system		

Returns

CTRL-A gate applied to the part target of state

```
6.1.3.13 applyCTRL() [2/2]
```

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

See also

```
qpp::Gates::CTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

state	Eigen expression	
Α	Eigen expression	
ctrl	Control subsystem indexes	
target	Subsystem indexes where the gate A is applied	
d	Subsystem dimensions	

Returns

CTRL-A gate applied to the part target of state

6.1.3.14 applyQFT()

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

Α	Eigen expression	
target	Subsystem indexes where the QFT is applied	
d	Subsystem dimensions	
swap	Swaps the qubits/qudits at the end (true by default)	

Returns

Qudit Quantum Fourier transform applied to the part target of A

6.1.3.15 applyTFQ()

Applies the inverse (adjoint) qudit quantum Fourier transform to the part *target* of the multi-partite state vector or density matrix *A*.

Parameters

Α	Eigen expression	
target	Subsystem indexes where the TFQ is applied	
d	Subsystem dimensions	
swap	Swaps the qubits/qudits at the end (true by default)	

Returns

Inverse (adjoint) qudit Quantum Fourier transform applied to the part target of A

6.1.3.16 avg()

Average.

prob	Real probability vector representing the probability distribution of X
X	Real random variable values represented by an STL-like container

Returns

Average of X

6.1.3.17 bloch2rho()

Computes the density matrix corresponding to the 3-dimensional real Bloch vector *r*.

See also

qpp::rho2bloch()

Parameters

r 3-dimensional real vector

Returns

Qubit density matrix

6.1.3.18 choi2kraus()

Orthogonal Kraus operators from Choi matrix.

See also

qpp::kraus2choi()

Extracts a set of orthogonal (under Hilbert-Schmidt operator norm) Kraus operators from the Choi matrix A

Note

The Kraus operators satisfy $Tr(K_i^\dagger K_j) = \delta_{ij}$ for all $i \neq j$

```
A Choi matrix
```

Returns

Set of orthogonal Kraus operators

6.1.3.19 choi2super()

Converts Choi matrix to superoperator matrix.

See also

qpp::super2choi()

Parameters

```
A Choi matrix
```

Returns

Superoperator matrix

6.1.3.20 comm()

Commutator.

See also

qpp::anticomm()

Commutator [A, B] = AB - BA. Both A and B must be Eigen expressions over the same scalar field.

Parameters

Α	Eigen expression
B	Eigen expression

Returns

Commutator AB-BA, as a dynamic matrix over the same scalar field as ${\it A}$

6.1.3.21 complement()

Constructs the complement of a subsystem vector.

Parameters

subsys	Subsystem vector
N	Total number of systems

Returns

Complement of subsys with respect to the set $\{0,1,\dots,N-1\}$

6.1.3.22 compperm()

Compose permutations.

Parameters

perm	Permutation
sigma	Permutation

Returns

Composition of the permutations *perm* o *sigma* = perm(sigma)

6.1.3.23 concurrence()

6.1 qpp Namespace Reference 39 Wootters concurrence of the bi-partite qubit mixed state A.

A Eigen expression

Returns

Wootters concurrence

6.1.3.24 conjugate()

Complex conjugate.

Parameters

A Eigen expression

Returns

Complex conjugate of A, as a dynamic matrix over the same scalar field as A

6.1.3.25 contfrac2x()

Real representation of a simple continued fraction.

See also

qpp::x2contfrac()

Note

If N is greater than the size of cf (by default it is), then all terms in cf are considered.

Parameters

	Integer vector containing the simple continued fraction expansion
Ν	Number of terms considered in the continued fraction expansion.

Real representation of the simple continued fraction

Convergents.

See also

qpp::contfrac2x() and qpp::x2contfrac()

Parameters

```
cf Continued fraction
```

Returns

Vector of convergents pairs (a_k, b_k) that approximate the number represented by the continued fraction

Convergents.

See also

```
qpp::contfrac2x() and qpp::x2contfrac()
```

Note

In the continued fraction expansion of x has less terms than N, then the series of convergents is truncated to the number of terms in the continued fraction expansion of x.

Parameters

Χ	Real number
N	Number of convergents.

Vector of convergents pairs (a_k,b_k) that approximate the number \emph{x}

6.1.3.28 cor()

Correlation.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels the rows, Y labels the columns)	
Χ	Real random variable values represented by an STL-like container	
Y	Real random variable values represented by an STL-like container	

Returns

Correlation of X and Y

6.1.3.29 cosm()

Matrix cos.

Parameters

```
A Eigen expression
```

Returns

Matrix cosine of A

6.1.3.30 cov()

Covariance.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels the rows, Y labels the columns)
Χ	Real random variable values represented by an STL-like container
Y	Real random variable values represented by an STL-like container

Returns

Covariance of X and Y

6.1.3.31 cwise()

Functor.

Parameters

Α	Eigen expression
f	Pointer-to-function from scalars of A to OutputScalar

Returns

Component-wise f(A), as a dynamic matrix over the $\operatorname{\it OutputScalar}$ scalar field

6.1.3.32 det()

Determinant.

A Eigen expression

Returns

Determinant of A, as a scalar over the same scalar field as A. Returns $\pm \infty$ when the determinant overflows/underflows.

Direct sum.

See also

qpp::dirsumpow()

Used to stop the recursion for the variadic template version of qpp::dirsum()

Parameters

```
head Eigen expression
```

Returns

Its argument head

```
6.1.3.34 dirsum() [2/4]
```

Direct sum.

See also

qpp::dirsumpow()

head	Eigen expression
tail Variadic Eigen expression (zero or more paramete	

Returns

Direct sum of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Direct sum.

See also

qpp::dirsumpow()

Parameters

```
As std::vector of Eigen expressions
```

Returns

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Direct sum.

See also

qpp::dirsumpow()

```
As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}
```

Returns

Direct sum of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.3.37 dirsumpow()

Direct sum power.

See also

qpp::dirsum()

Parameters

Α	Eigen expression
n	Non-negative integer

Returns

Direct sum of A with itself n times $A^{\oplus n}$, as a dynamic matrix over the same scalar field as A

Eigen expression ostream manipulator.

Parameters

Α	Eigen expression	
chop	Set to zero the elements smaller in absolute value than chop	

Instance of qpp::internal::IOManipEigen

Complex number ostream manipulator.

Parameters

Z	Complex number (or any other type implicitly cast-able to std::complex <double></double>	
chop	hop Set to zero the elements smaller in absolute value than chop	

Returns

Instance of qpp::internal::IOManipEigen

const std::string & end = "]")

Range ostream manipulator.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipRange

```
6.1.3.41 disp() [4/5]
```

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

Parameters

С	Container
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipRange

C-style pointer ostream manipulator.

Parameters

р	Pointer to the first element
N	Number of elements to be displayed
separator	Separator
start	Left marking
end	Right marking

Returns

Instance of qpp::internal::IOManipPointer

6.1.3.43 egcd()

Extended greatest common divisor of two integers.

See also

qpp::gcd()

Parameters

а	Integer
b	Integer

Returns

Tuple of: 1. Integer m, 2. Integer n, and 3. Non-negative integer gcd(a,b) such that ma + nb = gcd(a,b)

6.1.3.44 eig()

Full eigen decomposition.

See also

qpp::heig()

Parameters

A Eigen expression

Returns

Pair of: 1. Eigenvalues of *A*, as a complex dynamic column vector, and 2. Eigenvectors of *A*, as columns of a complex dynamic matrix

6.1.3.45 entanglement() [1/2]

```
template<typename Derived >
double qpp::entanglement (
```

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & dims )
```

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

```
qpp::entropy()
```

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Entanglement, with the logarithm in base 2

6.1.3.46 entanglement() [2/2]

Entanglement of the bi-partite pure state A.

Defined as the von-Neumann entropy of the reduced density matrix of one of the subsystems

See also

```
qpp::entropy()
```

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Entanglement, with the logarithm in base 2

von-Neumann entropy of the density matrix A

Parameters

```
A Eigen expression
```

Returns

von-Neumann entropy, with the logarithm in base 2

Shannon entropy of the probability distribution prob.

Parameters

```
prob Real probability vector
```

Returns

Shannon entropy, with the logarithm in base 2

6.1.3.49 evals()

Eigenvalues.

See also

qpp::hevals()

A Eigen expression

Returns

Eigenvalues of A, as a complex dynamic column vector

6.1.3.50 evects()

Eigenvectors.

See also

qpp::hevects()

Parameters

A Eigen expression

Returns

Eigenvectors of A, as columns of a complex dynamic matrix

6.1.3.51 expm()

Matrix exponential.

Parameters

A Eigen expression

Returns

Matrix exponential of A

```
6.1.3.52 factors()
```

Prime factor decomposition.

Note

Runs in $\mathcal{O}(\sqrt{n})$ time complexity

Parameters

a Integer different from 0, 1 or -1

Returns

Integer vector containing the factors

6.1.3.53 funm()

Functional calculus f(A)

Parameters

Α	Eigen expression
f	Pointer-to-function from complex to complex

Returns

f(A)

Greatest common divisor of two integers.

See also

qpp::lcm()

а	Integer
b	Integer

Returns

Greatest common divisor of a and b

Greatest common divisor of a list of integers.

See also

qpp::lcm()

Parameters

```
as List of integers
```

Returns

Greatest common divisor of all numbers in as

6.1.3.56 gconcurrence()

G-concurrence of the bi-partite pure state A.

Note

Both local dimensions must be equal

Uses qpp::logdet() to avoid overflows

See also

qpp::logdet()

A Eigen expression

Returns

G-concurrence

Gram-Schmidt orthogonalization.

Parameters

As std::vector of Eigen expressions as column vectors

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

Gram-Schmidt orthogonalization.

Parameters

As std::initializer_list of Eigen expressions as column vectors

Returns

Gram-Schmidt vectors of As as columns of a dynamic matrix over the same scalar field as its arguments

Gram-Schmidt orthogonalization.

Parameters

A Eigen expression, the input vectors are the columns of A

Returns

Gram-Schmidt vectors of the columns of A, as columns of a dynamic matrix over the same scalar field as A

6.1.3.60 heig()

Full eigen decomposition of Hermitian expression.

See also

qpp::eig()

Parameters

A Eigen expression

Returns

Pair of: 1. Eigenvalues of A, as a real dynamic column vector, and 2. Eigenvectors of A, as columns of a complex dynamic matrix

6.1.3.61 hevals()

Hermitian eigenvalues.

See also

qpp::evals()

```
A Eigen expression
```

Returns

Eigenvalues of Hermitian A, as a real dynamic column vector

6.1.3.62 hevects()

Eigenvectors of Hermitian matrix.

See also

qpp::evects()

Parameters

```
A Eigen expression
```

Returns

Eigenvectors of Hermitian matrix A, as columns of a complex matrix

6.1.3.63 inverse()

Inverse.

Parameters

```
A Eigen expression
```

Returns

Inverse of A, as a dynamic matrix over the same scalar field as A

6.1.3.64 invperm()

Inverse permutation.

Parameters

Returns

Inverse of the permutation perm

```
6.1.3.65 ip() [1/2]
```

Generalized inner product.

Parameters

phi	Column vector Eigen expression
psi	Column vector Eigen expression
subsys	Subsystem indexes over which phi is defined
dims	Dimensions of the multi-partite system

Returns

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

```
6.1.3.66 ip() [2/2]
```

Generalized inner product.

phi	Column vector Eigen expression
psi	Column vector Eigen expression
subsys	Subsystem indexes over which phi is defined
d	Subsystem dimensions

Returns

Inner product $\langle \phi_{subsys} | \psi \rangle$, as a scalar or column vector over the remaining Hilbert space

6.1.3.67 isprime()

Primality test based on the Miller-Rabin's algorithm.

Parameters

р	Integer different from 0, 1 or -1
k	Number of iterations. The probability of a false positive is 2^{-k} .

Returns

True if the number is (most-likely) prime, false otherwise

6.1.3.68 kraus2choi()

Choi matrix.

See also

qpp::choi2kraus()

Constructs the Choi matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|$, $|0\rangle\langle 1|$ etc.

Note

The superoperator matrix S and the Choi matrix C are related by $S_{ab,mn}=C_{ma,nb}$

Ks Set of Kraus operators

Returns

Choi matrix

6.1.3.69 kraus2super()

Superoperator matrix.

Constructs the superoperator matrix of the channel specified by the set of Kraus operators Ks in the standard operator basis $\{|i\rangle\langle j|\}$ ordered in lexicographical order, i.e. $|0\rangle\langle 0|$, $|0\rangle\langle 1|$ etc.

Parameters

Ks Set of Kraus operators

Returns

Superoperator matrix

```
6.1.3.70 kron() [1/4]
```

Kronecker product.

See also

qpp::kronpow()

Used to stop the recursion for the variadic template version of qpp::kron()

Parameters

head Eigen expression

Its argument head

Kronecker product.

See also

qpp::kronpow()

Parameters

head	Eigen expression
tail	Variadic Eigen expression (zero or more parameters)

Returns

Kronecker product of all input parameters, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Kronecker product.

See also

qpp::kronpow()

Parameters

As std::vector of Eigen expressions

Kronecker product of all elements in *As*, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

Kronecker product.

See also

qpp::kronpow()

Parameters

As std::initializer_list of Eigen expressions, such as {A1, A2, ..., Ak}

Returns

Kronecker product of all elements in As, evaluated from left to right, as a dynamic matrix over the same scalar field as its arguments

6.1.3.74 kronpow()

Kronecker power.

See also

qpp::kron()

Parameters

Α	Eigen expression
n	Non-negative integer

Kronecker product of A with itself n times $A^{\otimes n}$, as a dynamic matrix over the same scalar field as A

Least common multiple of two integers.

See also

```
qpp::gcd()
```

Parameters

а	Integer
b	Integer

Returns

Least common multiple of a and b

Least common multiple of a list of integers.

See also

```
qpp::gcd()
```

Parameters

```
as List of integers
```

Returns

Least common multiple of all numbers in as

6.1.3.77 load()

Loads Eigen matrix from a binary file (internal format) in double precision.

See also

```
qpp::save()
```

The template parameter cannot be automatically deduced and must be explicitly provided, depending on the scalar field of the matrix that is being loaded.

Example:

```
// loads a previously saved Eigen dynamic complex matrix from "input.bin"
cmat mat = load<cmat>("input.bin");
```

Parameters

fname Output file name

6.1.3.78 loadMATLAB() [1/2]

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

```
qpp::saveMATLAB()
```

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen ket
// from the MATLAB file "input.mat"
ket psi = loadMATLAB<ket>("input.mat");
```

Template Parameters

Derived Complex Eigen type

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be loaded

Returns

Eigen dynamic matrix

6.1.3.79 loadMATLAB() [2/2]

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

See also

qpp::saveMATLAB()

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// loads a previously saved Eigen dynamic double matrix
// from the MATLAB file "input.mat"
dmat mat = loadMATLAB<dmat>("input.mat");
```

Template Parameters

Derived	Non-complex Eigen type
---------	------------------------

Parameters

mat_file	MATALB .mat file
var_name	Variable name in the .mat file representing the matrix to be loaded

Returns

Eigen dynamic matrix

6.1.3.80 logdet()

Logarithm of the determinant.

Useful when the determinant overflows/underflows

Parameters

```
A Eigen expression
```

Returns

Logarithm of the determinant of A, as a scalar over the same scalar field as A

6.1.3.81 logm()

Matrix logarithm.

Parameters

```
A Eigen expression
```

Returns

Matrix logarithm of A

6.1.3.82 lognegativity() [1/2]

Logarithmic negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
dima	Dimensions of the bi partite system
aims	Dimensions of the bi-partite system

Logarithmic negativity, with the logarithm in base 2

Logarithmic negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Logarithmic negativity, with the logarithm in base 2

6.1.3.84 marginalX()

Marginal distribution.

Parameters

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels
	the rows, Ylabels the columns)

Returns

Real vector consisting of the marginal distribution of X

6.1.3.85 marginalY()

Marginal distribution.

probXY	Real matrix representing the joint probability distribution of X and Y in lexicographical order (X labels	1
	the rows, Y labels the columns)	

Returns

Real vector consisting of the marginal distribution of Y

Measures the state vector or density operator A using the set of Kraus operators Ks.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

```
6.1.3.87 measure() [2/9]
```

Measures the state vector or density matrix \boldsymbol{A} using the set of Kraus operators \boldsymbol{Ks} .

Parameters

Α	Eigen expression
Ks	Set of Kraus operators

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

Parameters

```
    Eigen expression
    Unitary matrix whose columns represent the measurement basis vectors
```

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.90 measure() [5/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

qpp::measure_seq()

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.92 measure() [7/9]

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

See also

```
qpp::measure_seq()
```

Note

The dimension of all *Ks* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Α	Eigen expression
Ks	Set of Kraus operators
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

6.1.3.93 measure() [8/9]

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

See also

```
qpp::measure_seq()
```

Note

The dimension of V must match the dimension of target. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

const std::vector< idx > & target,

Measures the part *target* of the multi-partite state vector or density matrix *A* in the orthonormal basis or rank-1 projectors specified by the columns of the matrix *V*.

See also

```
qpp::measure_seq()
```

idx d = 2)

Note

The dimension of *V* must match the dimension of *target*. The measurement is destructive, i.e. the measured subsystems are traced away.

Parameters

Α	Eigen expression
V	Matrix whose columns represent the measurement basis vectors or the bra parts of the rank-1 projectors
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Result of the measurement, 2. Vector of outcome probabilities, and 3. Vector of post-measurement normalized states

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

See also

qpp::measure()

Α	Eigen expression
target	Subsystem indexes that are measured
dims	Dimensions of the multi-partite system

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Sequentially measures the part *target* of the multi-partite state vector or density matrix A in the computational basis.

See also

qpp::measure()

Parameters

Α	Eigen expression
target	Subsystem indexes that are measured
d	Subsystem dimensions

Returns

Tuple of: 1. Vector of outcome results of the measurement (ordered in increasing order with respect to *target*, i.e. first measurement result corresponds to the subsystem with the smallest index), 2. Outcome probability, and 3. Post-measurement normalized state

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|\text{mask}\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

Parameters

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

Returns

Multi-partite qudit state vector, as a complex dynamic column vector

```
6.1.3.98 mket() [2/2] ket qpp::mket ( const std::vector< idx > & mask, idx d = 2) [inline]
```

Multi-partite qudit ket.

See also

```
qpp::operator "" _ket()
```

Constructs the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Multi-partite qudit state vector, as a complex dynamic column vector

6.1.3.99 modinv()

Modular inverse of a mod p.

See also

```
qpp::egcd()
```

Note

a and p must be co-prime

Parameters

а	Non-negative integer
р	Non-negative integer

Returns

```
Modular inverse a^{-1} \mod p
```

6.1.3.100 modmul()

```
bigint qpp::modmul (
          bigint a,
          bigint b,
          bigint p ) [inline]
```

Modular multiplication without overflow.

Computes $ab \bmod p$ without overflow

Parameters

а	Integer
b	Integer
р	Positive integer

Returns

 $ab \bmod p$ avoiding overflow

6.1.3.101 modpow()

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

Note

Uses qpp::modmul() that avoids overflows

Computes $a^n \mod p$

Parameters

а	Non-negative integer
n	Non-negative integer
р	Strictly positive integer

Returns

```
a^n \bmod p
```

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, where mask is a std::vector of non-negative integers. Each element in mask has to be smaller than the corresponding element in dims.

Parameters

mask	std::vector of non-negative integers
dims	Dimensions of the multi-partite system

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

Projector onto multi-partite qudit ket.

See also

```
qpp::operator "" _prj()
```

Constructs the projector onto the multi-partite qudit ket $|mask\rangle$, all subsystem having equal dimension d. mask is a std::vector of non-negative integers, and each element in mask has to be strictly smaller than d.

Parameters

mask	std::vector of non-negative integers
d	Subsystem dimensions

Returns

Projector onto multi-partite qudit state vector, as a complex dynamic matrix

6.1.3.104 multiidx2n()

```
idx qpp::multiidx2n ( const \ std::vector < \ idx \ > \ \& \ midx, const \ std::vector < \ idx \ > \ \& \ dims \ ) \quad [inline]
```

Multi-index to non-negative integer index.

See also

```
qpp::n2multiidx()
```

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

Parameters

midx	Multi-index
dims	Dimensions of the multi-partite system

Returns

Non-negative integer index

6.1.3.105 n2multiidx()

Non-negative integer index to multi-index.

See also

qpp::multiidx2n()

Uses standard lexicographical order, i.e. 00...0, 00...1 etc.

Parameters

n	Non-negative integer index
dims	Dimensions of the multi-partite system

Returns

Multi-index of the same size as dims

6.1.3.106 negativity() [1/2]

Negativity of the bi-partite mixed state A.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Negativity

6.1.3.107 negativity() [2/2]

Negativity of the bi-partite mixed state A.

Α	Eigen expression
d	Subsystem dimensions

Negativity

```
6.1.3.108 norm()
```

Frobenius norm.

Parameters

```
A Eigen expression
```

Returns

Frobenius norm of A

```
6.1.3.109 omega()
```

```
cplx qpp::omega (
    idx D ) [inline]
```

D-th root of unity.

Parameters

```
D Non-negative integer
```

Returns

D-th root of unity $\exp(2\pi i/D)$

```
6.1.3.110 operator""" _i()
```

User-defined literal for complex $i=\sqrt{-1}$ (real overload)

Example:

```
cplx z = 4.5_i; // type of z is std::complex<double>
```

6.1.3.111 powm()

Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.

See also

qpp::spectralpowm()

Explicitly multiplies the matrix A with itself n times. By convention $A^0 = I$.

Parameters

Α	Eigen expression
n	Non-negative integer

Returns

Matrix power A^n , as a dynamic matrix over the same scalar field as A

6.1.3.112 prj()

Projector.

Normalized projector onto state vector

Parameters

```
A Eigen expression
```

Returns

Projector onto the state vector A, or the matrix Zero if A has norm zero (i.e. smaller than qpp::eps), as a dynamic matrix over the same scalar field as A

Element-wise product of A.

Parameters

```
A Eigen expression
```

Returns

Element-wise product of A, as a scalar over the same scalar field as A

Element-wise product of an STL-like range.

Parameters

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Element-wise product of the range, as a scalar over the same scalar field as the range

Element-wise product of the elements of an STL-like container.

```
c STL-like container
```

Element-wise product of the elements of the container, as a scalar over the same scalar field as the container

Partial trace.

See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Returns

Partial trace $Tr_{subsys}(\cdot)$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

```
6.1.3.117 ptrace() [2/2]
```

Partial trace.

See also

```
qpp::ptrace1(), qpp::ptrace2()
```

Partial trace of the multi-partite state vector or density matrix over the list target of subsystems

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial trace $Tr_{subsys}(\cdot)$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.3.118 ptrace1() [1/2]

Partial trace.

See also

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Parameters

,	Α	Eigen expression
-	dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_A(\cdot)$ over the first subsystem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.119 ptrace1() [2/2]

Partial trace.

Sa	_	2	len
26	е	ы	180

qpp::ptrace2()

Partial trace over the first subsystem of bi-partite state vector or density matrix

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_A(\cdot)$ over the first subsytem A in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

Partial trace.

See also

```
qpp::ptrace1()
```

Partial trace over the second subsystem of bi-partite state vector or density matrix

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Partial trace $Tr_B(\cdot)$ over the second subsystem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

Partial trace.

See also

```
qpp::ptrace1()
```

Partial trace over the second subsystem of bi-partite state vector or density matrix

Α	Eigen expression
d	Subsystem dimensions

Returns

Partial trace $Tr_B(\cdot)$ over the second subsytem B in a bi-partite system $A\otimes B$, as a dynamic matrix over the same scalar field as A

6.1.3.122 ptranspose() [1/2]

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Parameters

Α	Eigen expression
target	Subsystem indexes
dims	Dimensions of the multi-partite system

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.3.123 ptranspose() [2/2]

Partial transpose.

Partial transpose of the multi-partite state vector or density matrix over the list target of subsystems

Α	Eigen expression
target	Subsystem indexes
d	Subsystem dimensions

Returns

Partial transpose $(\cdot)^{T_{subsys}}$ over the subsytems *target* in a multi-partite system, as a dynamic matrix over the same scalar field as A

6.1.3.124 QFT()

Qudit quantum Fourier transform.

Parameters

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Qudit quantum Fourier transform applied on A

6.1.3.125 qmutualinfo() [1/2]

Quantum mutual information between 2 subsystems of a composite system.

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
dims	Dimensions of the multi-partite system

Mutual information between the 2 subsystems

Quantum mutual information between 2 subsystems of a composite system.

Parameters

Α	Eigen expression
subsysA	Indexes of the first subsystem
subsysB	Indexes of the second subsystem
d	Subsystem dimensions

Returns

Mutual information between the 2 subsystems

Generates a random real number uniformly distributed in the interval [a, b)

Parameters

а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Returns

Random real number (double) uniformly distributed in the interval [a, b)

Generates a random big integer uniformly distributed in the interval [a, b].

Note

To avoid ambiguity with double qpp::rand(double, double) cast at least one of the arguments to qpp::bigint

Parameters

	Beginning of the interval, belongs to it
b	End of the interval, belongs to it

Returns

Random big integer uniformly distributed in the interval [a, b]

```
6.1.3.129 rand() [3/5]

template<typename Derived >
Derived qpp::rand (
    idx rows,
    idx cols,
    double a = 0,
    double b = 1)
```

Generates a random matrix with entries uniformly distributed in the interval [a, b)

If complex, then both real and imaginary parts are uniformly distributed in [a, b)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

```
6.1.3.130 rand() [4/5]

template<>>
dmat qpp::rand (
        idx rows,
        idx cols,
        double a,
        double b) [inline]
```

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries uniformly distributed in [-1,1)
dmat mat = rand<dmat>(3, 3, -1, 1);
```

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
а	Beginning of the interval, belongs to it
b	End of the interval, does not belong to it

Returns

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd, 
// with entries (both real and imaginary) uniformly distributed in [-1,1) cmat mat = rand<cmat>(3, 3, -1, 1);
```

Parameters

rows	Number of rows of the random generated matrix	
cols	Number of columns of the random generated matrix	
а	Beginning of the interval, belongs to it	
b	End of the interval, does not belong to it	

Returns

Random complex matrix

6.1.3.132 randH()

```
cmat qpp::randH (
    idx D = 2 ) [inline]
```

Generates a random Hermitian matrix.

D Dimension of the Hilbert space

Returns

Random Hermitian matrix

6.1.3.133 randidx()

```
idx qpp::randidx (
        idx a = std::numeric_limits<idx>::min(),
        idx b = std::numeric_limits<idx>::max() ) [inline]
```

Generates a random index (idx) uniformly distributed in the interval [a, b].

Parameters

a Beginning of the interval, belongs to itb End of the interval, belongs to it

Returns

Random index (idx) uniformly distributed in the interval [a, b]

6.1.3.134 randket()

```
ket qpp::randket (
    idx D = 2 ) [inline]
```

Generates a random normalized ket (pure state vector)

Parameters

D Dimension of the Hilbert space

Returns

Random normalized ket

6.1.3.135 randkraus()

```
std::vector<cmat> qpp::randkraus (
    idx N,
    idx D = 2 ) [inline]
```

Generates a set of random Kraus operators.

Note

The set of Kraus operators satisfy the closure condition $\sum_i K_i^\dagger K_i = I$

Parameters

Ν	Number of Kraus operators
D	Dimension of the Hilbert space

Returns

Set of N Kraus operators satisfying the closure condition

```
6.1.3.136 randn() [1/4]

template<typename Derived >
Derived qpp::randn (
    idx rows,
    idx cols,
    double mean = 0,
    double sigma = 1)
```

Generates a random matrix with entries normally distributed in N(mean, sigma)

If complex, then both real and imaginary parts are normally distributed in N(mean, sigma)

This is the generic version that always throws qpp::Exception::Type::UNDEFINED_TYPE. It is specialized only for qpp::dmat and qpp::cmat

```
6.1.3.137 randn() [2/4]

template<>>
dmat qpp::randn (
        idx rows,
        idx cols,
        double mean,
        double sigma ) [inline]
```

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXd,
// with entries normally distributed in N(0,2)
dmat mat = randn<dmat>(3, 3, 0, 2);
```

rows	Number of rows of the random generated matrix	
cols	Number of columns of the random generated matrix	
mean	Mean	
sigma	Standard deviation	

Returns

Random real matrix

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

The template parameter cannot be automatically deduced and must be explicitly provided

Example:

```
// generates a 3 x 3 random Eigen::MatrixXcd, 
// with entries (both real and imaginary) normally distributed in N(0,2) cmat mat = randn<cmat>(3, 3, 0, 2);
```

Parameters

rows	Number of rows of the random generated matrix
cols	Number of columns of the random generated matrix
mean	Mean
sigma	Standard deviation

Returns

Random complex matrix

Generates a random real number (double) normally distributed in N(mean, sigma)

Parameters

mean	Mean
sigma	Standard deviation

Returns

Random real number normally distributed in N(mean, sigma)

6.1.3.140 randperm()

```
std::vector<idx> qpp::randperm (
    idx N ) [inline]
```

Generates a random uniformly distributed permutation.

Uses Knuth shuffle method (as implemented by std::shuffle), so that all permutations are equally probable

Parameters

```
N Size of the permutation
```

Returns

Random permutation of size N

6.1.3.141 randprime()

```
bigint qpp::randprime (
          bigint a,
          bigint b,
          idx N = 1000 ) [inline]
```

Generates a random big prime uniformly distributed in the interval [a, b].

а	Beginning of the interval, belongs to it
b End of the interval, belongs to it	
N	Maximum number of candidates

Random big integer uniformly distributed in the interval [a, b]

6.1.3.142 randprob()

```
\begin{tabular}{ll} \tt std::vector<double> qpp::randprob ( & idx N) & [inline] \end{tabular}
```

Generates a random probability vector uniformly distributed over the probability simplex.

Parameters

N Size of the probability vector

Returns

Random probability vector

6.1.3.143 randrho()

```
cmat qpp::randrho (
    idx D = 2) [inline]
```

Generates a random density matrix.

Parameters

D | Dimension of the Hilbert space

Returns

Random density matrix

6.1.3.144 randU()

```
cmat qpp::randU (
    idx D = 2) [inline]
```

Generates a random unitary matrix.

D Dimension of the Hilbert space

Returns

Random unitary

6.1.3.145 randV()

Generates a random isometry matrix.

Parameters

Din	Size of the input Hilbert space
Dout	Size of the output Hilbert space

Returns

Random isometry matrix

```
6.1.3.146 renyi() [1/2]
```

Renyi- α entropy of the density matrix ${\it A}$, for $\alpha \geq 0$.

Note

When $\alpha \to 1$ the Renyi entropy converges to the von-Neumann entropy, with the logarithm in base 2

Α	Eigen expression	
alpha	A Non-negative real number, use app::infty for $lpha=\infty$	

Renyi- α entropy, with the logarithm in base 2

Renyi- α entropy of the probability distribution *prob*, for $\alpha \geq 0$.

Note

When $\alpha \to 1$ the Renyi entropy converges to the Shannon entropy, with the logarithm in base 2

Parameters

prob	Real probability vector	
alpha	Non-negative real number, use qpp::infty for $\alpha = \infty$	

Returns

Renyi- α entropy, with the logarithm in base 2

6.1.3.148 reshape()

Reshape.

Uses column-major order when reshaping (same as MATLAB)

Α	Eigen expression
rows	Number of rows of the reshaped matrix
cols	Number of columns of the reshaped matrix

Reshaped matrix with rows rows and cols columns, as a dynamic matrix over the same scalar field as A

6.1.3.149 rho2bloch()

Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

See also

qpp::bloch2rho()

Note

It is implicitly assumed that the density matrix is Hermitian

Parameters

```
A Eigen expression
```

Returns

3-dimensional Bloch vector

6.1.3.150 rho2pure()

Finds the pure state representation of a matrix proportional to a projector onto a pure state.

Note

No purity check is done, the input state A must have rank one, otherwise the function returns the first non-zero eigenvector of A

Parameters

A Eigen expression, assumed to be proportional to a projector onto a pure state, i.e. A is assumed to have rank one

The unique non-zero eigenvector of A (up to a phase), as a dynamic column vector over the same scalar field as A

6.1.3.151 save()

Saves Eigen expression to a binary file (internal format) in double precision.

See also

qpp::load()

Parameters

Α	Eigen expression
fname	Output file name

6.1.3.152 saveMATLAB() [1/2]

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

qpp::loadMATLAB()

Template Parameters

Complex	Eigen type
1	3 - 71 -

Α	Eigen expression over the complex field
---	---

mat_file	MATALB .mat file	
var_name	Variable name in the .mat file representing the matrix to be saved	
mode	Saving mode (append, overwrite etc.), see MATLAB <i>matOpen()</i> documentation for details	

6.1.3.153 saveMATLAB() [2/2]

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.

See also

qpp::loadMATLAB()

Template Parameters

Npn-complex	Eigen type
-------------	------------

Parameters

Α	Non-complex Eigen expression
mat_file	MATALB .mat file
var_name Variable name in the .mat file representing the matrix to be saved	
mode	Saving mode (append, overwrite etc.), see MATLAB matOpen() documentation for details

6.1.3.154 schatten()

Schatten matrix norm.

	Α	Eigen expression
ĺ	р	Real number, greater or equal to 1, use qpp::infty for $p = \infty$

Schatten-p matrix norm of A

Schmidt basis on Alice side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix \boldsymbol{U} whose columns represent the Schmidt basis vectors on Alice side.

Schmidt basis on Alice side.

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix ${\cal U}$ whose columns represent the Schmidt basis vectors on Alice side.

6.1.3.157 schmidtB() [1/2] template<typename Derived >

cmat qpp::schmidtB (

```
const Eigen::MatrixBase< Derived > & A,
const std::vector< idx > & dims )
```

Schmidt basis on Bob side.

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

Schmidt basis on Bob side.

idx d = 2)

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Unitary matrix ${\cal V}$ whose columns represent the Schmidt basis vectors on Bob side.

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.160 schmidtcoeffs() [2/2]

Schmidt coefficients of the bi-partite pure state A.

Note

The sum of the squares of the Schmidt coefficients equals 1

See also

qpp::schmidtprobs()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Schmidt coefficients of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.161 schmidtprobs() [1/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Parameters

Α	Eigen expression
dims	Dimensions of the bi-partite system

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.3.162 schmidtprobs() [2/2]

Schmidt probabilities of the bi-partite pure state A.

Defined as the squares of the Schmidt coefficients. The sum of the Schmidt probabilities equals 1.

See also

qpp::schmidtcoeffs()

Parameters

Α	Eigen expression
d	Subsystem dimensions

Returns

Real vector consisting of the Schmidt probabilites of A, ordered in decreasing order

6.1.3.163 sigma()

Standard deviation.

prob	Real probability vector representing the probability distribution of X
X	Real random variable values represented by an STL-like container

Returns

Standard deviation of X

6.1.3.164 sinm()

Matrix sin.

Parameters

A Eigen expression

Returns

Matrix sine of A

6.1.3.165 spectralpowm()

Matrix power.

See also

qpp::powm()

Uses the spectral decomposition of \emph{A} to compute the matrix power. By convention $\emph{A}^0 = \emph{I}$.

Α	Eigen expression
Z	Complex number

Matrix power A^z

6.1.3.166 sqrtm()

Matrix square root.

Parameters

```
A Eigen expression
```

Returns

Matrix square root of A

```
6.1.3.167 sum() [1/3]
```

Element-wise sum of A.

Parameters

```
A Eigen expression
```

Returns

Element-wise sum of A, as a scalar over the same scalar field as A

```
6.1.3.168 sum() [2/3]
```

Element-wise sum of an STL-like range.

first	Iterator to the first element of the range
last	Iterator to the last element of the range

Returns

Element-wise sum of the range, as a scalar over the same scalar field as the range

Element-wise sum of the elements of an STL-like container.

Parameters

```
c STL-like container
```

Returns

Element-wise sum of the elements of the container, as a scalar over the same scalar field as the container

6.1.3.170 super2choi()

Converts superoperator matrix to Choi matrix.

See also

qpp::choi2super()

Parameters

A Superoperator matrix

Choi matrix

6.1.3.171 svals()

Singular values.

Parameters

A Eigen expression

Returns

Singular values of A, ordered in decreasing order, as a real dynamic column vector

6.1.3.172 svd()

Full singular value decomposition.

Parameters

A Eigen expression

Returns

Tuple of: 1. Left sigular vectors of A, as columns of a complex dynamic matrix, 2. Singular values of A, ordered in decreasing order, as a real dynamic column vector, and 3. Right singular vectors of A, as columns of a complex dynamic matrix

6.1.3.173 svdU()

Left singular vectors.

```
A Eigen expression
```

Returns

Complex dynamic matrix, whose columns are the left singular vectors of A

6.1.3.174 svdV()

Right singular vectors.

Parameters

```
A Eigen expression
```

Returns

Complex dynamic matrix, whose columns are the right singular vectors of A

6.1.3.175 syspermute() [1/2]

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Α	Eigen expression
perm	Permutation
dims	Dimensions of the multi-partite system

Permuted system, as a dynamic matrix over the same scalar field as A

Subsystem permutation.

Permutes the subsystems of a state vector or density matrix. The qubit perm[i] is permuted to the location i.

Parameters

Α	Eigen expression
perm	Permutation
d	Subsystem dimensions

Returns

Permuted system, as a dynamic matrix over the same scalar field as A

6.1.3.177 TFQ()

Inverse (adjoint) qudit quantum Fourier transform.

Parameters

Α	Eigen expression
d	Subsystem dimensions
swap	Swaps the qubits/qudits at the end (true by default)

Returns

Inverse (adjoint) qudit quantum Fourier transform applied on A

6.1.3.178 trace()

Trace.

Parameters

```
A Eigen expression
```

Returns

Trace of A, as a scalar over the same scalar field as A

6.1.3.179 transpose()

Transpose.

Parameters

```
A Eigen expression
```

Returns

Transpose of A, as a dynamic matrix over the same scalar field as A

```
6.1.3.180 tsallis() [1/2] template<typename Derived > double qpp::tsallis ( const Eigen::MatrixBase< Derived > & A, double q)
```

Tsallis- q entropy of the density matrix A, for $q \ge 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the von-Neumann entropy, with the logarithm in base e

Parameters

Α	Eigen expression	
q	Non-negative real number	

Returns

Tsallis- q entropy

Tsallis- q entropy of the probability distribution prob, for $q \ge 0$.

Note

When $q \to 1$ the Tsallis entropy converges to the Shannon entropy, with the logarithm in base e

Parameters

prob	Real probability vector
q	Non-negative real number

Returns

Tsallis- q entropy

6.1.3.182 uniform()

```
std::vector<double> qpp::uniform (
    idx N ) [inline]
```

Uniform probability distribution vector.

Parameters

N Size of the alphabet

Returns

Real vector consisting of a uniform distribution of size N

6.1.3.183 var()

Variance.

Parameters

prob	Real probability vector representing the probability distribution of X
Χ	Real random variable values represented by an STL-like container

Returns

Variance of X

6.1.3.184 x2contfrac()

Simple continued fraction expansion.

See also

```
qpp::contfrac2x()
```

Parameters

X	Real number
Ν	Maximum number of terms in the expansion
cut	Stop the expansion when the next term is greater than cut

Returns

Integer vector containing the simple continued fraction expansion of x. If there are M less than N terms in the expansion, a shorter vector with M components is returned.

6.1.4 Variable Documentation

6.1.4.1 chop

```
constexpr double qpp::chop = 1e-10
```

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

6.1.4.2 ee

```
constexpr double qpp::ee = 2.718281828459045235360287471352662497
```

Base of natural logarithm, e.

6.1.4.3 eps

```
constexpr double qpp::eps = 1e-12
```

Used to decide whether a number or expression in double precision is zero or not.

Example:

```
if(std::abs(x) < qpp::eps) // x is zero</pre>
```

6.1.4.4 idx_infty

```
const idx qpp::idx_infty = static_cast<idx>(-1)
```

Used to denote the largest unsigned index.

6.1.4.5 infty

```
constexpr double qpp::infty = std::numeric_limits<double>::max()
```

Used to denote infinity in double precision.

6.1.4.6 maxn

```
constexpr idx qpp::maxn = 64
```

Maximum number of allowed qubits/qudits (subsystems)

Used internally to allocate arrays on the stack (for performance reasons):

6.1.4.7 pi

```
constexpr double qpp::pi = 3.141592653589793238462643383279502884
```

 π

6.2 qpp::exception Namespace Reference

Quantum++ exception hierarchy namespace.

Classes

• class CustomException

Custom exception.

· class DimsInvalid

Invalid dimension(s) exception.

· class DimsMismatchCvector

Dimension(s) mismatch column vector size exception.

• class DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

· class DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

· class DimsMismatchVector

Dimension(s) mismatch vector size exception.

class DimsNotEqual

Dimensions not equal exception.

· class Duplicates

System (e.g. std::vector) has duplicates exception.

class Exception

Base class for generating Quantum++ custom exceptions.

class InvalidIterator

Invalid iterator.

• class MatrixMismatchSubsys

Matrix mismatch subsystems exception.

• class MatrixNotCvector

Matrix is not a column vector exception.

class MatrixNotRvector

Matrix is not a row vector exception.

class MatrixNotSquare

Matrix is not square exception.

· class MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

class MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

· class MatrixNotSquareNorVector

Matrix is not square nor vector exception.

· class MatrixNotVector

Matrix is not a vector exception.

class NoCodeword

Codeword does not exist exception.

· class NotBipartite

Not bi-partite exception.

· class NotImplemented

Code not yet implemented.

class NotQubitCvector

Column vector is not 2 x 1 exception.

class NotQubitMatrix

Matrix is not 2 x 2 exception.

· class NotQubitRvector

Row vector is not 1 x 2 exception.

class NotQubitSubsys

Subsystems are not qubits exception.

class NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

class OutOfRange

Argument out of range exception.

class PermInvalid

Invalid permutation exception.

· class PermMismatchDims

Permutation mismatch dimensions exception.

class QuditAlreadyMeasured

Qudit was already measured exception.

· class SizeMismatch

Size mismatch exception.

• class SubsysMismatchDims

Subsystems mismatch dimensions exception.

class TypeMismatch

Type mismatch exception.

class UndefinedType

Not defined for this type exception.

• class Unknown

Unknown exception.

class ZeroSize

Object has zero size exception.

6.2.1 Detailed Description

Quantum++ exception hierarchy namespace.

6.3 qpp::experimental Namespace Reference

Experimental/test functions/classes, do not use or modify.

6.3.1 Detailed Description

Experimental/test functions/classes, do not use or modify.

6.4 qpp::internal Namespace Reference

Internal utility functions, do not use them directly or modify them.

Classes

- struct Display Impl
- · class IOManipEigen
- · class IOManipPointer
- · class IOManipRange
- · class Singleton

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Functions

- void n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- $\bullet \ \ \text{template}{<} \text{typename Derived} >$

bool check_square_mat (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ \mathsf{template} \mathord{<} \mathsf{typename} \ \mathsf{Derived} >$

bool bool check_vector (const Eigen::MatrixBase Derived > &A)

• template<typename Derived >

bool check_rvector (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ \text{template}{<} \text{typename Derived} >$

bool check_cvector (const Eigen::MatrixBase< Derived > &A)

• template<typename T >

bool check_nonzero_size (const T &x) noexcept

- template<typename T1 , typename T2 >

bool check_matching_sizes (const T1 &lhs, const T2 &rhs) noexcept

- bool check_dims (const std::vector< idx > &dims)
- template<typename Derived >

 $bool\ check_dims_match_mat\ (const\ std::vector < idx > \&dims,\ const\ Eigen::MatrixBase < Derived > \&A)$

• template<typename Derived >

bool check_dims_match_cvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool check dims match rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- bool check_eq_dims (const std::vector< idx > &dims, idx dim) noexcept
- bool check_no_duplicates (std::vector< idx > v)
- bool check_subsys_match_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)

```
    template < typename Derived >
        bool check_qubit_matrix (const Eigen::MatrixBase < Derived > &A) noexcept
```

template<typename Derived >

bool check_qubit_cvector (const Eigen::MatrixBase< Derived > &A) noexcept
• template<typename Derived >

bool check_qubit_rvector (const Eigen::MatrixBase< Derived > &A) noexcept

- template<typename Derived >
 bool check_qubit_vector (const Eigen::MatrixBase< Derived > &A) noexcept
- bool check_perm (const std::vector< idx > &perm)
- template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > kron2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::
 MatrixBase< Derived2 > &B)
- template<typename Derived1, typename Derived2 >
 dyn_mat< typename Derived1::Scalar > dirsum2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen
 ::MatrixBase< Derived2 > &B)
- template<typename T >
 void variadic_vector_emplace (std::vector< T > &)
- template < typename T, typename First, typename... Args > void variadic_vector_emplace (std::vector < T > &v, First &&first, Args &&... args)
- idx get_num_subsys (idx sz, idx d)
- idx get_dim_subsys (idx sz, idx N)

6.4.1 Detailed Description

Internal utility functions, do not use them directly or modify them.

6.4.2 Function Documentation

6.4.2.1 check_cvector()

6.4.2.2 check_dims()

```
bool qpp::internal::check_dims (  const \ std::vector < \ idx \ > \ \& \ dims \ ) \quad [inline]
```

6.4.2.3 check_dims_match_cvect()

6.4.2.4 check_dims_match_mat()

6.4.2.5 check_dims_match_rvect()

6.4.2.6 check_eq_dims()

6.4.2.7 check_matching_sizes()

6.4.2.8 check_no_duplicates()

```
bool qpp::internal::check_no_duplicates ( {\tt std::vector} < {\tt idx} \, > \, v \; ) \quad [{\tt inline}]
```

```
6.4.2.9 check_nonzero_size()
template<typename T >
bool qpp::internal::check_nonzero_size (
            const T & x ) [noexcept]
6.4.2.10 check_perm()
bool qpp::internal::check_perm (
            const std::vector< idx > & perm ) [inline]
6.4.2.11 check_qubit_cvector()
template<typename Derived >
bool qpp::internal::check_qubit_cvector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.12 check_qubit_matrix()
template<typename Derived >
bool qpp::internal::check_qubit_matrix (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.13 check_qubit_rvector()
template<typename Derived >
bool qpp::internal::check_qubit_rvector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
6.4.2.14 check_qubit_vector()
template<typename Derived >
bool qpp::internal::check_qubit_vector (
            const Eigen::MatrixBase< Derived > & A ) [noexcept]
```

```
6.4.2.15 check_rvector()
```

```
template<typename Derived >
bool qpp::internal::check_rvector (
            const Eigen::MatrixBase< Derived > & A )
6.4.2.16 check_square_mat()
template<typename Derived >
bool qpp::internal::check_square_mat (
            const Eigen::MatrixBase< Derived > & A )
6.4.2.17 check_subsys_match_dims()
bool qpp::internal::check_subsys_match_dims (
            const std::vector< idx > & subsys,
            const std::vector< idx > & dims ) [inline]
6.4.2.18 check_vector()
template<typename Derived >
bool qpp::internal::check_vector (
            const Eigen::MatrixBase< Derived > & A )
6.4.2.19 dirsum2()
template<typename Derived1 , typename Derived2 >
dyn_mat<typename Derived1::Scalar> qpp::internal::dirsum2 (
            const Eigen::MatrixBase< Derived1 > & A,
            const Eigen::MatrixBase< Derived2 > & B )
6.4.2.20 get_dim_subsys()
idx qpp::internal::get_dim_subsys (
            idx sz,
             idx N ) [inline]
```

6.4.2.21 get_num_subsys()

```
idx qpp::internal::get_num_subsys (
            idx sz,
             idx d ) [inline]
6.4.2.22 kron2()
template<typename Derived1 , typename Derived2 >
dyn_mat<typename Derived1::Scalar> qpp::internal::kron2 (
            const Eigen::MatrixBase< Derived1 > & A,
             const Eigen::MatrixBase< Derived2 > & B )
6.4.2.23 multiidx2n()
idx qpp::internal::multiidx2n (
             const idx *const midx,
             idx numdims,
             const idx *const dims ) [inline], [noexcept]
6.4.2.24 n2multiidx()
void qpp::internal::n2multiidx (
             idx n,
             idx numdims,
             const idx *const dims,
             idx * result ) [inline], [noexcept]
6.4.2.25 variadic_vector_emplace() [1/2]
template<typename T >
void qpp::internal::variadic_vector_emplace (
            std::vector< T > & )
6.4.2.26 variadic_vector_emplace() [2/2]
template<typename T , typename First , typename... Args>
void qpp::internal::variadic_vector_emplace (
             std::vector< T > & v,
             First && first,
```

Args &&... args)

6.5 qpp::literals Namespace Reference

Functions

```
• constexpr cplx operator"" _i (unsigned long long int x) noexcept \textit{User-defined literal for complex } i = \sqrt{-1} \textit{ (integer overload)}
```

```
template<char... Bits>
ket operator"" _ket ()
```

Multi-partite qubit ket user-defined literal.

template<char... Bits> bra operator"" _bra ()

Multi-partite qubit bra user-defined literal.

template<char... Bits> cmat operator"" _prj ()

Multi-partite qubit projector user-defined literal.

6.5.1 Function Documentation

```
6.5.1.1 operator"""_bra()

template<char... Bits>
bra qpp::literals::operator"" _bra ( )
```

Multi-partite qubit bra user-defined literal.

See also

```
qpp::mket() and qpp::adjoint()
```

Constructs the multi-partite qubit bra $\langle \mathrm{Bits}|$

Template Parameters

```
Bits String of binary numbers representing the qubit bra
```

Returns

Multi-partite qubit bra, as a complex dynamic row vector

User-defined literal for complex $i = \sqrt{-1}$ (integer overload)

Example:

```
cplx z = 4_i; // type of z is std::complex<double>
```

6.5.1.3 operator""" _ket()

```
template<char... Bits>
ket qpp::literals::operator"" _ket ( )
```

Multi-partite qubit ket user-defined literal.

See also

qpp::mket()

Constructs the multi-partite qubit ket $|Bits\rangle$

Template Parameters

Bits	String of binary numbers representing the qubit ket
------	---

Returns

Multi-partite qubit ket, as a complex dynamic column vector

6.5.1.4 operator""" _prj()

```
template<char... Bits>
cmat qpp::literals::operator"" _prj ( )
```

Multi-partite qubit projector user-defined literal.

See also

qpp::mprj()

Constructs the multi-partite qubit projector $|\mathrm{Bits}\rangle\langle\mathrm{Bits}|$ (in the computational basis)

Template Parameters

Bits String of binary numbers representing the qubit state to project on

\mathbf{L}	ΔT	 rn	c

Multi-partite qubit projector, as a complex dynamic matrix

Chapter 7


Class Documentation

7.1 qpp::Bit_circuit Class Reference


Classical reversible circuit simulator.

#include <classes/reversible.h>

Inheritance diagram for qpp::Bit_circuit:



Collaboration diagram for qpp::Bit_circuit:



Classes

struct Gate_count

Public Member Functions

• Bit_circuit (const Dynamic_bitset &dynamic_bitset)

Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.

Bit_circuit & X (idx pos)

Bit flip.

Bit_circuit & NOT (idx pos)

Bit flip

• Bit_circuit & CNOT (const std::vector< idx > &pos)

Controlled-NOT.

Bit_circuit & TOF (const std::vector < idx > &pos)

Toffoli gate.

Bit_circuit & SWAP (const std::vector < idx > &pos)

Swap bits.

Bit_circuit & FRED (const std::vector < idx > &pos)

Fredkin gate (Controlled-SWAP)

• Bit_circuit & reset () noexcept

Reset the circuit all zero, clear all gates.

Public Attributes

• struct qpp::Bit_circuit::Gate_count gate_count

Gate counters.

Additional Inherited Members

7.1.1 Detailed Description

Classical reversible circuit simulator.

7.1.2 Constructor & Destructor Documentation

7.1.2.1 Bit_circuit()

Conversion constructor, used to initialize a qpp::Bit_circuit with a qpp::Dynamic_bitset.

Parameters

```
dynamic_bitset | Dynamic bitset
```

7.1.3 Member Function Documentation

7.1.3.1 CNOT()

Controlled-NOT.

Parameters

```
pos Bit position in the circuit
```

Returns

Reference to the current instance

7.1.3.2 FRED()

Fredkin gate (Controlled-SWAP)

Parameters

```
pos Bit positions in the circuit, in the order control-target-target
```

Returns

Reference to the current instance

```
7.1.3.3 NOT()
```

```
Bit_circuit& qpp::Bit_circuit::NOT (
        idx pos ) [inline]
```

Bit flip.

See also

```
qpp::Bit_circuit::X()
```

Parameters

```
pos Bit position in the circuit
```

Returns

Reference to the current instance

```
7.1.3.4 reset()
```

```
Bit_circuit& qpp::Bit_circuit::reset ( ) [inline], [noexcept]
```

Reset the circuit all zero, clear all gates.

Returns

Reference to the current instance

```
7.1.3.5 SWAP()
```

Swap bits.

Parameters

pos Bit positions in the circuit

Returns

Reference to the current instance

7.1.3.6 TOF()

Toffoli gate.

Parameters

pos | Bit positions in the circuit, in the order control-control-target

Returns

Reference to the current instance

7.1.3.7 X()

Bit flip.

See also

qpp::Bit_circuit::NOT()

Parameters

pos Bit position in the circuit

Returns

Reference to the current instance

7.1.4 Member Data Documentation

7.1.4.1 gate_count

struct qpp::Bit_circuit::Gate_count qpp::Bit_circuit::gate_count

Gate counters.

The documentation for this class was generated from the following file:


· classes/reversible.h

7.2 qpp::Codes Class Reference


const Singleton class that defines quantum error correcting codes

#include <classes/codes.h>

Inheritance diagram for qpp::Codes:



Collaboration diagram for qpp::Codes:



Public Types

enum Type { Type::FIVE_QUBIT = 1, Type::SEVEN_QUBIT_STEANE, Type::NINE_QUBIT_SHOR }
 Code types, add more codes here if needed.

Public Member Functions

ket codeword (Type type, idx i) const
 Returns the codeword of the specified code type.

Private Member Functions

• Codes ()

Default constructor.

∼Codes ()=default

Default destructor.

Friends

class internal::Singleton < const Codes >

Additional Inherited Members

7.2.1 Detailed Description

const Singleton class that defines quantum error correcting codes

7.2.2 Member Enumeration Documentation

7.2.2.1 Type

```
enum qpp::Codes::Type [strong]
```

Code types, add more codes here if needed.

See also

qpp::Codes::codeword()

Enumerator

FIVE_QUBIT	[[5,1,3]] qubit code
SEVEN_QUBIT_STEANE	[[7,1,3]] Steane qubit code
NINE_QUBIT_SHOR	[[9,1,3]] Shor qubit code

Generated by Doxygen

7.2.3 Constructor & Destructor Documentation

7.2.3.1 Codes()

```
qpp::Codes::Codes ( ) [inline], [private]
```

Default constructor.

7.2.3.2 ∼Codes()

```
qpp::Codes::~Codes ( ) [private], [default]
```

Default destructor.

7.2.4 Member Function Documentation

7.2.4.1 codeword()

Returns the codeword of the specified code type.

See also

```
qpp::Codes::Type
```

Parameters

type	Code type
i	Codeword index

Returns

i-th codeword of the code type

7.2.5 Friends And Related Function Documentation

7.2.5.1 internal::Singleton < const Codes >

```
friend class internal::Singleton< const Codes > [friend]
```

The documentation for this class was generated from the following file:


· classes/codes.h

7.3 qpp::exception::CustomException Class Reference


Custom exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::CustomException:



Collaboration diagram for qpp::exception::CustomException:



Public Member Functions

· CustomException (const std::string &where, const std::string &what)

Private Member Functions

std::string type_description () const override
 Exception type description.

Private Attributes

std::string what_{{}}

7.3.1 Detailed Description

Custom exception.

Custom exception, the user must provide a custom message

7.3.2 Constructor & Destructor Documentation

7.3.2.1 CustomException()

7.3.3 Member Function Documentation

7.3.3.1 type_description()

```
std::string qpp::exception::CustomException::type_description ( ) const [inline], [override],
[private], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

7.3.4 Member Data Documentation

7.3.4.1 what_

```
std::string qpp::exception::CustomException::what_ {} [private]
```

The documentation for this class was generated from the following file:


· classes/exception.h

7.4 qpp::exception::DimsInvalid Class Reference


Invalid dimension(s) exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsInvalid:



Collaboration diagram for qpp::exception::DimsInvalid:



Public Member Functions

• std::string type_description () const override Exception type description.

7.4.1 Detailed Description

Invalid dimension(s) exception.

std::vector<idx> of dimensions has zero size or contains zeros

7.4.2 Member Function Documentation

7.4.2.1 type_description()

std::string qpp::exception::DimsInvalid::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


• classes/exception.h

7.5 qpp::exception::DimsMismatchCvector Class Reference


Dimension(s) mismatch column vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchCvector:



Collaboration diagram for qpp::exception::DimsMismatchCvector:



Public Member Functions

• std::string type_description () const override Exception type description.

7.5.1 Detailed Description

Dimension(s) mismatch column vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a column vector)

7.5.2 Member Function Documentation

7.5.2.1 type_description()

std::string qpp::exception::DimsMismatchCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.6 qpp::exception::DimsMismatchMatrix Class Reference


Dimension(s) mismatch matrix size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchMatrix:



Collaboration diagram for qpp::exception::DimsMismatchMatrix:



Public Member Functions

std::string type_description () const override
 Exception type description.

7.6.1 Detailed Description

Dimension(s) mismatch matrix size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of rows of the Eigen::Matrix (assumed to be a square matrix)

7.6.2 Member Function Documentation

7.6.2.1 type_description()

std::string qpp::exception::DimsMismatchMatrix::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.7 qpp::exception::DimsMismatchRvector Class Reference


Dimension(s) mismatch row vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchRvector:



Collaboration diagram for qpp::exception::DimsMismatchRvector:



Public Member Functions

std::string type_description () const override
 Exception type description.

7.7.1 Detailed Description

Dimension(s) mismatch row vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row vector)

7.7.2 Member Function Documentation

7.7.2.1 type_description()

std::string qpp::exception::DimsMismatchRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.8 qpp::exception::DimsMismatchVector Class Reference


Dimension(s) mismatch vector size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsMismatchVector:



Collaboration diagram for qpp::exception::DimsMismatchVector:



Public Member Functions

std::string type_description () const override
 Exception type description.

7.8.1 Detailed Description

Dimension(s) mismatch vector size exception.

Product of the elements of std::vector<idx> of dimensions is not equal to the number of elements of the Eigen::

Matrix (assumed to be a row/column vector)

7.8.2 Member Function Documentation

7.8.2.1 type_description()

std::string qpp::exception::DimsMismatchVector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.9 qpp::exception::DimsNotEqual Class Reference


Dimensions not equal exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::DimsNotEqual:



Collaboration diagram for qpp::exception::DimsNotEqual:



Public Member Functions

• std::string type_description () const override Exception type description.

7.9.1 Detailed Description

Dimensions not equal exception.

Local/global dimensions are not equal

7.9.2 Member Function Documentation

7.9.2.1 type_description()

std::string qpp::exception::DimsNotEqual::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

· classes/exception.h

7.10 qpp::internal::Display_Impl_ Struct Reference

```
#include <internal/util.h>
```

Inheritance diagram for qpp::internal::Display_Impl_:



Public Member Functions

template<typename T >
 std::ostream & display_impl_ (const T &A, std::ostream &os, double chop=qpp::chop) const

7.10.1 Member Function Documentation

7.10.1.1 display_impl_()

The documentation for this struct was generated from the following file:


• internal/util.h

7.11 qpp::exception::Duplicates Class Reference


System (e.g. std::vector) has duplicates exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Duplicates:



Collaboration diagram for qpp::exception::Duplicates:



Public Member Functions

• std::string type_description () const override Exception type description.

7.11.1 Detailed Description

System (e.g. std::vector) has duplicates exception.

7.11.2 Member Function Documentation

7.11.2.1 type_description()

std::string qpp::exception::Duplicates::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.12 qpp::Dynamic_bitset Class Reference


Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

#include <classes/reversible.h>

Inheritance diagram for qpp::Dynamic bitset:



Collaboration diagram for qpp::Dynamic_bitset:



Public Types

• using value_type = unsigned int

Type of the storage elements.

using storage_type = std::vector< value_type >

Type of the storage.

Public Member Functions

Dynamic_bitset (idx N)

Constructor, initializes all bits to false (zero)

· const storage_type & data () const

Raw storage space of the bitset.

• idx size () const noexcept

Number of bits stored in the bitset.

idx storage_size () const noexcept

Size of the underlying storage space (in units of value_type, unsigned int by default)

idx count () const noexcept

Number of bits set to one in the bitset (Hamming weight)

• bool get (idx pos) const noexcept

The value of the bit at position pos.

• bool none () const noexcept

Checks whether none of the bits are set.

• bool all () const noexcept

Checks whether all bits are set.

· bool any () const noexcept

Checks whether any bit is set.

• Dynamic_bitset & set (idx pos, bool value=true)

Sets the bit at position pos.

Dynamic_bitset & set () noexcept

Set all bits to true.

• Dynamic_bitset & rand (idx pos, double p=0.5)

Sets the bit at position pos according to a Bernoulli(p) distribution.

• Dynamic_bitset & rand (double p=0.5)

Sets all bits according to a Bernoulli(p) distribution.

• Dynamic bitset & reset (idx pos)

Sets the bit at position pos to false.

• Dynamic_bitset & reset () noexcept

Sets all bits to false.

Dynamic_bitset & flip (idx pos)

Flips the bit at position pos.

• Dynamic_bitset & flip () noexcept

Flips all bits.

bool operator== (const Dynamic_bitset &rhs) const noexcept

Equality operator.

• bool operator!= (const Dynamic_bitset &rhs) const noexcept

Inequality operator.

idx operator- (const Dynamic bitset &rhs) const noexcept

Number of places the two bitsets differ (Hamming distance)

template < class CharT = char, class Traits = std::char_traits < CharT>, class Allocator = std::allocator < CharT>> std::basic_string < CharT, Traits, Allocator > to_string (CharT zero=CharT('0'), CharT one=CharT('1')) const String representation.

Protected Member Functions

• idx index_ (idx pos) const

Index of the pos bit in the storage space.

• idx offset_ (idx pos) const

Offset of the pos bit in the storage space relative to its index.

Protected Attributes

· idx storage_size_

Storage size.

idx N_

Number of bits.

std::vector< value_type > v_

Storage space.

Private Member Functions

std::ostream & display (std::ostream &os) const override
 qpp::IDisplay::display() override, displays the bitset bit by bit

7.12.1 Detailed Description

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

7.12.2 Member Typedef Documentation

```
7.12.2.1 storage_type
```

```
using qpp::Dynamic_bitset::storage_type = std::vector<value_type>
```

Type of the storage.

7.12.2.2 value_type

```
using qpp::Dynamic_bitset::value_type = unsigned int
```

Type of the storage elements.

7.12.3 Constructor & Destructor Documentation

7.12.3.1 Dynamic_bitset()

```
qpp::Dynamic_bitset::Dynamic_bitset (
          idx N ) [inline]
```

Constructor, initializes all bits to false (zero)

Parameters

N Number of bits in the bitset

7.12.4 Member Function Documentation

```
7.12.4.1 all()
```

```
bool qpp::Dynamic_bitset::all ( ) const [inline], [noexcept]
```

Checks whether all bits are set.

Returns

True if all of the bits are set

```
7.12.4.2 any()
```

```
bool qpp::Dynamic_bitset::any ( ) const [inline], [noexcept]
```

Checks whether any bit is set.

Returns

True if any of the bits is set

7.12.4.3 count()

```
idx qpp::Dynamic_bitset::count ( ) const [inline], [noexcept]
```

Number of bits set to one in the bitset (Hamming weight)

Returns

Hamming weight

7.12.4.4 data()

```
const storage_type& qpp::Dynamic_bitset::data ( ) const [inline]
```

Raw storage space of the bitset.

Returns

Const reference to the underlying storage space

7.12.4.5 display()

qpp::IDisplay::display() override, displays the bitset bit by bit

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

Flips the bit at position *pos*.

Parameters

```
pos Position in the bitset
```

Returns

Reference to the current instance

```
7.12.4.7 flip() [2/2]
Dynamic_bitset& qpp::Dynamic_bitset::flip ( ) [inline], [noexcept]
```

Flips all bits.

Returns

Reference to the current instance

```
7.12.4.8 get()
```

```
bool qpp::Dynamic_bitset::get (
          idx pos ) const [inline], [noexcept]
```

The value of the bit at position pos.

Parameters

pos Position in the bitset

Returns

The value of the bit at position pos

7.12.4.9 index_()

Index of the pos bit in the storage space.

Parameters

```
pos Bit location
```

Returns

Index of the pos bit in the storage space

7.12.4.10 none()

```
bool qpp::Dynamic_bitset::none ( ) const [inline], [noexcept]
```

Checks whether none of the bits are set.

Returns

True if none of the bits are set

7.12.4.11 offset_()

Offset of the *pos* bit in the storage space relative to its index.

Parameters



Returns

Offset of the pos bit in the storage space relative to its index

7.12.4.12 operator"!=()

Inequality operator.

Parameters

rhs Dynamic_bitset against which the inequality is being tested

Returns

True if the bitsets are not equal (bit by bit), false otherwise

7.12.4.13 operator-()

Number of places the two bitsets differ (Hamming distance)

Parameters

rhs Dynamic_bitset against which the Hamming distance is computed

Returns

Hamming distance

7.12.4.14 operator==()

Equality operator.

Parameters

rhs Dynamic_bitset against which the equality is being tested

Returns

True if the bitsets are equal (bit by bit), false otherwise

7.12.4.15 rand() [1/2]

```
Dynamic_bitset& qpp::Dynamic_bitset::rand ( idx \ pos, double \ p = 0.5 \ ) \ [inline]
```

Sets the bit at position pos according to a Bernoulli(p) distribution.

Parameters

pos	Position in the bitset
р	Probability

Returns


Reference to the current instance

7.12.4.16 rand() [2/2]

```
\label{eq:double_p} \begin{split} & \texttt{Dynamic\_bitset\& qpp::Dynamic\_bitset::rand (} \\ & & \texttt{double} \ p = \textit{0.5} \ ) \quad [inline] \end{split}
```

Sets all bits according to a Bernoulli(p) distribution.

Parameters



Returns

Reference to the current instance

```
7.12.4.17 reset() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::reset (
        idx pos ) [inline]
```

Sets the bit at position pos to false.

Parameters

pos Position in the bitset

Returns

Reference to the current instance

```
7.12.4.18 reset() [2/2]
```

Dynamic_bitset& qpp::Dynamic_bitset::reset () [inline], [noexcept]

Sets all bits to false.

Returns

Reference to the current instance

```
7.12.4.19 set() [1/2]
```

```
Dynamic_bitset& qpp::Dynamic_bitset::set (
        idx pos,
        bool value = true ) [inline]
```

Sets the bit at position pos.

Parameters

pos	Position in the bitset
value	Bit value

Returns

Reference to the current instance

```
7.12.4.20 set() [2/2]

Dynamic_bitset& qpp::Dynamic_bitset::set ( ) [inline], [noexcept]
```

Set all bits to true.

Returns

Reference to the current instance

7.12.4.21 size()

```
idx qpp::Dynamic_bitset::size ( ) const [inline], [noexcept]
```

Number of bits stored in the bitset.

Returns

Number of bits stored in the bitset

7.12.4.22 storage_size()

```
idx qpp::Dynamic_bitset::storage_size ( ) const [inline], [noexcept]
```

Size of the underlying storage space (in units of value_type, unsigned int by default)

Returns

Size of the underlying storage space

7.12.4.23 to_string()

String representation.

Template Parameters

CharT	String character type
Traits	String traits
Gе д¢∤⊘је⊴∤ уугD	x % ₱₱ng Allocator

Parameters

zero	Character representing the zero
one	Character representing the one

Returns

The bitset as a string

7.12.5 Member Data Documentation

```
7.12.5.1 N_
```

```
idx qpp::Dynamic_bitset::N_ [protected]
```

Number of bits.

7.12.5.2 storage_size_

```
idx qpp::Dynamic_bitset::storage_size_ [protected]
```

Storage size.

7.12.5.3 v_

```
std::vector<value_type> qpp::Dynamic_bitset::v_ [protected]
```

Storage space.

The documentation for this class was generated from the following file:


• classes/reversible.h

7.13 qpp::exception::Exception Class Reference


Base class for generating Quantum++ custom exceptions.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Exception:



Collaboration diagram for qpp::exception::Exception:



Public Member Functions

• Exception (const std::string &where)

Constructs an exception.

• virtual const char * what () const noexcept override

Overrides std::exception::what()

• virtual std::string type_description () const =0

Exception type description.

Private Attributes

- std::string where_
- std::string msg_

7.13.1 Detailed Description

Base class for generating Quantum++ custom exceptions.

Derive from this class if more exceptions are needed, making sure to override qpp::exception::Exception::type_ description() in the derived class and to inherit the constructor qpp::exception::Exception::Exception(). Preferably keep your newly defined exception classes in the namespace qpp::exception.

Example:

```
namespace qpp
{
  namespace exception
  {
    class ZeroSize : public Exception
      {
        public:
            std::string type_description() const override
            {
                 return "Object has zero size";
            }
            // inherit the base class' qpp::exception::Exception constructor
            using Exception::Exception;
        };
} // namespace exception
} // namespace qpp
```

7.13.2 Constructor & Destructor Documentation

7.13.2.1 Exception()

Constructs an exception.

Parameters

where Text representing where the exception occurred

7.13.3 Member Function Documentation

7.13.3.1 type_description()

```
std::string qpp::exception::Exception::type_description ( ) const [inline], [pure virtual]
```

Exception type description.

Returns

Exception type description

Implemented in qpp::exception::InvalidIterator, qpp::exception::NotImplemented, qpp::exception::Custom ← Exception, qpp::exception::Duplicates, qpp::exception::QuditAlreadyMeasured, qpp::exception::UndefinedType,

qpp::exception::SizeMismatch, qpp::exception::TypeMismatch, qpp::exception::OutOfRange, qpp::exception::NotOdeword, qpp::exception::NotBipartite, qpp::exception::NotQubitSubsys, qpp::exception::NotQubitVector, qpp⇔::exception::NotQubitRvector, qpp::exception::NotQubitCvector, qpp::exception::NotQubitMatrix, qpp::exception⇔::PermMismatchDims, qpp::exception::PermInvalid, qpp::exception::SubsysMismatchDims, qpp::exception⇔::DimsMismatchVector, qpp::exception::DimsMismatchCvector, qpp⇔::exception::DimsMismatchMatrix, qpp::exception::DimsNotEqual, qpp::exception::DimsInvalid, qpp::exception⇔::MatrixMismatchSubsys, qpp::exception::MatrixNotSquareNorVector, qpp::exception::MatrixNotSquareNorCvector, qpp::exception::MatrixNotVector, qpp::exception::MatrixNotVector, qpp::exception::MatrixNotVector, qpp::exception::MatrixNotVector, qpp::exception::ZeroSize, and qpp::exception::Unknown.

7.13.3.2 what()

virtual const char* qpp::exception::Exception::what () const [inline], [override], [virtual],
[noexcept]

Overrides std::exception::what()

Returns

Exception description

7.13.4 Member Data Documentation

```
7.13.4.1 msg
```

std::string qpp::exception::Exception::msg_ [mutable], [private]

7.13.4.2 where

std::string qpp::exception::Exception::where_ [private]

The documentation for this class was generated from the following file:

· classes/exception.h

7.14 qpp::Bit_circuit::Gate_count Struct Reference

#include <classes/reversible.h>

Public Attributes

- idx NOT = 0
- idx & X = NOT
- idx CNOT = 0
- idx SWAP = 0
- idx FRED = 0
- idx TOF = 0

7.14.1 Member Data Documentation

7.14.1.1 CNOT

```
idx qpp::Bit_circuit::Gate_count::CNOT = 0
```

7.14.1.2 FRED

```
idx qpp::Bit_circuit::Gate_count::FRED = 0
```

7.14.1.3 NOT

```
idx qpp::Bit_circuit::Gate_count::NOT = 0
```

7.14.1.4 SWAP

```
idx qpp::Bit_circuit::Gate_count::SWAP = 0
```

7.14.1.5 TOF

```
idx qpp::Bit_circuit::Gate_count::TOF = 0
```

7.14.1.6 X

```
idx& qpp::Bit_circuit::Gate_count::X = NOT
```

The documentation for this struct was generated from the following file:


· classes/reversible.h

7.15 qpp::Gates Class Reference


const Singleton class that implements most commonly used gates

```
#include <classes/gates.h>
```

Inheritance diagram for qpp::Gates:



Collaboration diagram for qpp::Gates:



Public Member Functions

cmat Rn (double theta, const std::vector< double > &n) const

Qubit rotation of theta about the 3-dimensional real (unit) vector n.

cmat RX (double theta) const

Qubit rotation of theta about the X axis.

cmat RY (double theta) const

Qubit rotation of theta about the Y axis.

cmat RZ (double theta) const

Qubit rotation of theta about the Z axis.

• cmat Zd (idx D=2) const

Generalized Z gate for qudits.

• cmat SWAPd (idx D=2) const

SWAP gate for qudits.

• cmat Fd (idx D=2) const

Quantum Fourier transform gate for qudits.

• cmat MODMUL (idx a, idx N, idx n) const

Modular multiplication gate for qubits Implements $|x\rangle \longrightarrow |ax \bmod N\rangle$.

• cmat Xd (idx D=2) const

Generalized X gate for qudits.

• template<typename Derived = Eigen::MatrixXcd>

Derived Id (idx D=2) const

Identity gate.

template<typename Derived >

dyn_mat< typename Derived::Scalar > CTRL (const Eigen::MatrixBase< Derived > &A, const std::vector<
idx > &ctrl, const std::vector< idx > &target, idx n, idx d=2) const

Generates the multi-partite multiple-controlled-A gate in matrix form.

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const
std::vector< idx > &dims) const

Expands out.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, const std::initializer list< idx > &dims) const

Expands out.

template<typename Derived >

dyn_mat< typename Derived::Scalar > expandout (const Eigen::MatrixBase< Derived > &A, idx pos, idx n,
idx d=2) const

Expands out.

std::string get_name (const cmat &U) const

Get the name of the most common qubit gates.

Public Attributes

cmat Id2 {cmat::Identity(2, 2)}

Identity gate.

cmat H {cmat::Zero(2, 2)}

Hadamard gate.

cmat X {cmat::Zero(2, 2)}

Pauli Sigma-X gate.

cmat Y {cmat::Zero(2, 2)}

```
Pauli Sigma-Y gate.

    cmat Z {cmat::Zero(2, 2)}

     Pauli Sigma-Z gate.

    cmat S {cmat::Zero(2, 2)}

     S gate.

    cmat T {cmat::Zero(2, 2)}

      T gate.
cmat CNOT {cmat::ldentity(4, 4)}
     Controlled-NOT control target gate.
cmat CZ {cmat::Identity(4, 4)}
     Controlled-Phase gate.
cmat CNOTba {cmat::Zero(4, 4)}
     Controlled-NOT target->control gate.
• cmat SWAP {cmat::Identity(4, 4)}
     SWAP gate.
• cmat TOF {cmat::ldentity(8, 8)}
      Toffoli gate.
cmat FRED {cmat::Identity(8, 8)}
     Fredkin gate.
```

Private Member Functions

• Gates ()

Initializes the gates.

• ∼Gates ()=default

Default destructor.

Friends

class internal::Singleton < const Gates >

Additional Inherited Members

7.15.1 Detailed Description

const Singleton class that implements most commonly used gates

7.15.2 Constructor & Destructor Documentation

```
7.15.2.1 Gates()

qpp::Gates::Gates ( ) [inline], [private]
```

Initializes the gates.

7.15.2.2 \sim Gates()

```
qpp::Gates::~Gates ( ) [private], [default]
```

Default destructor.

7.15.3 Member Function Documentation

7.15.3.1 CTRL()

Generates the multi-partite multiple-controlled-A gate in matrix form.

See also

```
qpp::applyCTRL()
```

Note

The dimension of the gate A must match the dimension of target

Parameters

Α	Eigen expression
ctrl	Control subsystem indexes
target	Subsystem indexes where the gate A is applied
n	Total number of subsystems
d	Subsystem dimensions

Returns

CTRL-A gate, as a matrix over the same scalar field as A

7.15.3.2 expandout() [1/3]

```
template<typename Derived >
dyn_mat<typename Derived::Scalar> qpp::Gates::expandout (
```

```
const Eigen::MatrixBase< Derived > & A,
idx pos,
const std::vector< idx > & dims ) const [inline]
```

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

Α	Eigen expression
pos	Position
dims	Dimensions of the multi-partite system

Returns

Tensor product $I \otimes \cdots \otimes I \otimes A \otimes I \otimes \cdots \otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.15.3.3 expandout() [2/3]

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Note

The std::initializer_list overload exists because otherwise, in the degenerate case when *dims* has only one element, the one element list is implicitly converted to the element's underlying type, i.e. qpp::idx, which has the net effect of picking the wrong (non-vector) qpp::expandout() overload

Parameters

Α	Eigen expression
pos	Position
dims	Dimensions of the multi-partite system

Returns

Tensor product $I\otimes\cdots\otimes I\otimes A\otimes I\otimes\cdots\otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.15.3.4 expandout() [3/3]

Expands out.

See also

qpp::kron()

Expands out A as a matrix in a multi-partite system. Faster than using qpp::kron(I, I, ..., I, A, I, ..., I).

Parameters

Α	Eigen expression
pos	Position
n	Number of subsystems
d	Subsystem dimensions

Returns

Tensor product $I \otimes \cdots \otimes I \otimes A \otimes I \otimes \cdots \otimes I$, with A on position pos, as a dynamic matrix over the same scalar field as A

7.15.3.5 Fd()

```
cmat qpp::Gates::Fd (
    idx D = 2 ) const [inline]
```

Quantum Fourier transform gate for qudits.

Note

```
Defined as F = \sum_{j,k=0}^{D-1} \exp(2\pi \mathrm{i} jk/D) |j\rangle\langle k|
```

Parameters

D Dimension of the Hilbert space

Returns

Fourier transform gate for qudits

7.15.3.6 get_name()

Get the name of the most common qubit gates.

Note

Assumes that the gate U is represented by a square matrix. If not, returns the empty string

Parameters

U Complex matrix representing the quantum gate

Returns

The name of the gate (if any), otherwise the empty string

7.15.3.7 Id()

```
template<typename Derived = Eigen::MatrixXcd>
Derived qpp::Gates::Id (
    idx D = 2 ) const [inline]
```

Identity gate.

Note

Can change the return type from complex matrix (default) by explicitly specifying the template parameter

Parameters

D Dimension of the Hilbert space

Returns

Identity gate on a Hilbert space of dimension D

7.15.3.8 MODMUL()

```
cmat qpp::Gates::MODMUL (
          idx a,
          idx N,
          idx n ) const [inline]
```

Modular multiplication gate for qubits Implements $|x\rangle \longrightarrow |ax \bmod N\rangle$.

Note

For the gate to be unitary, *a* and *N* should be co-prime. The function does not check co-primality in release versions!

The number of qubits required to implement the gate should satisfy $n \geq \lceil \log_2(N) \rceil$

Parameters

а	Positive integer less than N
N	Positive integer
n	Number of qubits required for implementing the gate

Returns

Modular multiplication gate

7.15.3.9 Rn()

Qubit rotation of *theta* about the 3-dimensional real (unit) vector *n*.

Parameters

theta	Rotation angle
n	3-dimensional real (unit) vector

Returns

Rotation gate

7.15.3.10 RX()

Qubit rotation of theta about the X axis.

Parameters

theta	Rotation angle
-------	----------------

Returns

Rotation gate

7.15.3.11 RY()

Qubit rotation of theta about the Y axis.

Parameters

theta Rotation angle

Returns

Rotation gate

7.15.3.12 RZ()

Qubit rotation of theta about the Z axis.

Parameters

theta	Rotation angle

Returns

Rotation gate

7.15.3.13 SWAPd()

```
cmat qpp::Gates::SWAPd (
    idx D = 2 ) const [inline]
```

SWAP gate for qudits.

Parameters

D Dimension of the Hilbert space

Returns

SWAP gate for qudits

7.15.3.14 Xd()

```
cmat qpp::Gates::Xd (
    idx D = 2 ) const [inline]
```

Generalized X gate for qudits.

Note

```
Defined as X=\sum_{j=0}^{D-1}|j\oplus 1\rangle\langle j|, i.e. raising operator X|j\rangle=|j\oplus 1\rangle
```

Parameters

D Dimension of the Hilbert space

Returns

Generalized X gate for qudits

7.15.3.15 Zd()

```
cmat qpp::Gates::Zd (
        idx D = 2 ) const [inline]
```

Generalized Z gate for qudits.

Note

```
Defined as Z = \sum_{j=0}^{D-1} \exp(2\pi \mathrm{i} j/D) |j\rangle\langle j|
```

Parameters

D Dimension of the Hilbert space

Returns

Generalized Z gate for qudits

7.15.4 Friends And Related Function Documentation

```
7.15.4.1 internal::Singleton < const Gates >
```

```
friend class internal::Singleton< const Gates > [friend]
```

7.15.5 Member Data Documentation

7.15.5.1 CNOT

```
cmat qpp::Gates::CNOT {cmat::Identity(4, 4)}
```

Controlled-NOT control target gate.

7.15.5.2 CNOTba

```
cmat qpp::Gates::CNOTba {cmat::Zero(4, 4)}
```

Controlled-NOT target->control gate.

7.15.5.3 CZ

```
cmat qpp::Gates::CZ {cmat::Identity(4, 4)}
```

Controlled-Phase gate.

```
7.15.5.4 FRED
cmat qpp::Gates::FRED {cmat::Identity(8, 8)}
Fredkin gate.
7.15.5.5 H
cmat qpp::Gates::H {cmat::Zero(2, 2)}
Hadamard gate.
7.15.5.6 Id2
cmat qpp::Gates::Id2 {cmat::Identity(2, 2)}
Identity gate.
7.15.5.7 S
cmat qpp::Gates::S {cmat::Zero(2, 2)}
S gate.
7.15.5.8 SWAP
cmat qpp::Gates::SWAP {cmat::Identity(4, 4)}
SWAP gate.
7.15.5.9 T
cmat qpp::Gates::T {cmat::Zero(2, 2)}
```

T gate.

```
7.15.5.10 TOF
```

```
cmat qpp::Gates::TOF {cmat::Identity(8, 8)}
```

Toffoli gate.

7.15.5.11 X

```
cmat qpp::Gates::X {cmat::Zero(2, 2)}
```

Pauli Sigma-X gate.

7.15.5.12 Y

```
cmat qpp::Gates::Y {cmat::Zero(2, 2)}
```

Pauli Sigma-Y gate.

7.15.5.13 Z

```
cmat qpp::Gates::Z {cmat::Zero(2, 2)}
```

Pauli Sigma-Z gate.


The documentation for this class was generated from the following file:

classes/gates.h

7.16 qpp::QCircuitDescription::GateStep Struct Reference

One step consisting only of gates/operators in the circuit.

Collaboration diagram for qpp::QCircuitDescription::GateStep:



Public Member Functions

• GateStep ()=default

Default constructor.

GateStep (GateType gate_type, const cmat &gate, const std::vector < idx > &ctrl, const std::vector < idx > &target, idx step_no, std::string name="")

Constructs a gate step instance.

Public Attributes

```
• GateType gate_type_ = GateType::NONE
```

gate type

• cmat gate_

gate

std::vector< idx > ctrl_

control

std::vector < idx > target_

target where the gate is being applied

idx step_no_

step number

• std::string name_

custom name of the step

7.16.1 Detailed Description

One step consisting only of gates/operators in the circuit.

7.16.2 Constructor & Destructor Documentation

```
7.16.2.1 GateStep() [1/2]
```

```
qpp::QCircuitDescription::GateStep::GateStep ( ) [default]
```

Default constructor.

7.16.2.2 GateStep() [2/2]

Constructs a gate step instance.

Parameters

gate_type	Gate type
gate	Quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes
step_no	Circuit step number
name	Optional gate name

7.16.3 Member Data Documentation

```
7.16.3.1 ctrl_
```

```
std::vector<idx> qpp::QCircuitDescription::GateStep::ctrl_
```

control

```
7.16.3.2 gate_
cmat qpp::QCircuitDescription::GateStep::gate_
gate
7.16.3.3 gate_type_
GateType qpp::QCircuitDescription::GateStep::gate_type_ = GateType::NONE
gate type
7.16.3.4 name
std::string qpp::QCircuitDescription::GateStep::name_
custom name of the step
7.16.3.5 step_no_
idx qpp::QCircuitDescription::GateStep::step_no_
step number
7.16.3.6 target_
std::vector<idx> qpp::QCircuitDescription::GateStep::target_
target where the gate is being applied
The documentation for this struct was generated from the following file:
```

Generated by Doxygen


· classes/circuits.h

7.17 qpp::IDisplay Class Reference

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

#include <classes/idisplay.h>

Inheritance diagram for qpp::IDisplay:



Public Member Functions

• IDisplay ()=default

Default constructor.

IDisplay (const IDisplay &)=default

Default copy constructor.

• IDisplay (IDisplay &&)=default

Default move constructor.

• IDisplay & operator= (const IDisplay &)=default

Default copy assignment operator.

IDisplay & operator= (IDisplay &&)=default

Default move assignment operator.

• virtual \sim IDisplay ()=default

Default virtual destructor.

Private Member Functions

virtual std::ostream & display (std::ostream &os) const =0
 Must be overridden by all derived classes.

Friends

std::ostream & operator<< (std::ostream &os, const IDisplay &rhs)
 Overloads the extraction operator.

7.17.1 Detailed Description

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

This class defines friend inline std::ostream& operator<< (std::ostream& os, const qpp::IDisplay& rhs). The latter delegates the work to the pure private virtual function qpp::IDisplay::display() which has to be overridden by all derived classes.

7.17.2 Constructor & Destructor Documentation

```
7.17.2.1 | IDisplay() [1/3]

qpp::IDisplay::IDisplay ( ) [default]
```

Default constructor.

Default copy constructor.

Default move constructor.

```
7.17.2.4 ~|Display()
virtual qpp::IDisplay::~IDisplay ( ) [virtual], [default]
```

Default virtual destructor.

7.17.3 Member Function Documentation

```
7.17.3.1 display()
```

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implemented in qpp::QCircuit, qpp::QCircuitDescription, qpp::Dynamic_bitset, qpp::QCircuitDescription::iterator ← ::value_type_, qpp::internal::IOManipEigen, qpp::Timer < T, CLOCK_T >, qpp::internal::IOManipPointer < Pointer ← Type >, and qpp::internal::IOManipRange < InputIterator >.

```
7.17.3.2 operator=() [1/2]
```

Default copy assignment operator.

```
7.17.3.3 operator=() [2/2]
```

Default move assignment operator.

7.17.4 Friends And Related Function Documentation

```
7.17.4.1 operator <<
```

Overloads the extraction operator.

Delegates the work to the virtual function qpp::IDisplay::display()

The documentation for this class was generated from the following file:


classes/idisplay.h

7.18 qpp::Init Class Reference


const Singleton class that performs additional initializations/cleanups

```
#include <classes/init.h>
```

Inheritance diagram for qpp::Init:



Collaboration diagram for qpp::Init:



Private Member Functions

- Init ()
 - Additional initializations.
- ∼Init ()
 - Cleanups.

Friends

• class internal::Singleton< const Init >

Additional	Inherited	Members
------------	-----------	---------

7.18.1 Detailed Description

const Singleton class that performs additional initializations/cleanups

7.18.2 Constructor & Destructor Documentation

```
7.18.2.1 Init()
```

```
qpp::Init::Init ( ) [inline], [private]
```

Additional initializations.

7.18.2.2 ∼Init()

```
qpp::Init::~Init ( ) [inline], [private]
```

Cleanups.

7.18.3 Friends And Related Function Documentation

7.18.3.1 internal::Singleton < const Init >

```
friend class internal::Singleton< const Init > [friend]
```

The documentation for this class was generated from the following file:


· classes/init.h

7.19 qpp::exception::InvalidIterator Class Reference


Invalid iterator.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::InvalidIterator:



Collaboration diagram for qpp::exception::InvalidIterator:



Public Member Functions

• std::string type_description () const override Exception type description.

7.19.1 Detailed Description

Invalid iterator.

7.19.2 Member Function Documentation

7.19.2.1 type_description()

std::string qpp::exception::InvalidIterator::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

· classes/exception.h


7.20 qpp::internal::IOManipEigen Class Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipEigen:



Collaboration diagram for qpp::internal::IOManipEigen:



Public Member Functions

- template<typename Derived >
 IOManipEigen (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
- IOManipEigen (const cplx z, double chop=qpp::chop)

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- cmat A_
- double chop_

7.20.1 Constructor & Destructor Documentation

```
7.20.1.1 IOManipEigen() [1/2]
```

7.20.1.2 IOManipEigen() [2/2]

7.20.2 Member Function Documentation

7.20.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.20.3 Member Data Documentation

7.20.3.1 A_

```
cmat qpp::internal::IOManipEigen::A_ [private]
```

7.20.3.2 chop_

```
double qpp::internal::IOManipEigen::chop_ [private]
```


The documentation for this class was generated from the following file:

internal/classes/iomanip.h


7.21 qpp::internal::IOManipPointer< PointerType > Class Template Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipPointer< PointerType >:



Collaboration diagram for qpp::internal::IOManipPointer< PointerType >:



Public Member Functions

- IOManipPointer (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")
- IOManipPointer (const IOManipPointer &)=default
- IOManipPointer & operator= (const IOManipPointer &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

```
const PointerType * p_
idx N_
std::string separator_
std::string start_
std::string end_
```

7.21.1 Constructor & Destructor Documentation

7.21.2 Member Function Documentation

7.21.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.21.2.2 operator=()

7.21.3 Member Data Documentation

```
7.21.3.1 end_

template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::end_ [private]

7.21.3.2 N_

template<typename PointerType>
idx qpp::internal::IOManipPointer< PointerType >::N_ [private]
```

7.21.3.3 p_

```
template<typename PointerType>
const PointerType* qpp::internal::IOManipPointer< PointerType >::p_ [private]
```

7.21.3.4 separator_

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::separator_ [private]
```

7.21.3.5 start_

```
template<typename PointerType>
std::string qpp::internal::IOManipPointer< PointerType >::start_ [private]
```


The documentation for this class was generated from the following file:

• internal/classes/iomanip.h


7.22 qpp::internal::IOManipRange < InputIterator > Class Template Reference

#include <internal/classes/iomanip.h>

Inheritance diagram for qpp::internal::IOManipRange< InputIterator >:



 $Collaboration\ diagram\ for\ qpp::internal::IOManipRange < Input Iterator >:$



Public Member Functions

- IOManipRange (InputIterator first, InputIterator last, const std::string &separator, const std::string &start="[", const std::string &end="]")
- IOManipRange (const IOManipRange &)=default
- IOManipRange & operator= (const IOManipRange &)=default

Private Member Functions

std::ostream & display (std::ostream &os) const override
 Must be overridden by all derived classes.

Private Attributes

- InputIterator first_
- InputIterator last
- std::string separator
- · std::string start_
- std::string end_

7.22.1 Constructor & Destructor Documentation

```
7.22.1.1 IOManipRange() [1/2]
```

7.22.1.2 IOManipRange() [2/2]

7.22.2 Member Function Documentation

7.22.2.1 display()

Must be overridden by all derived classes.

The actual stream extraction processing is performed by the overriden member function in the derived class. This function is automatically invoked by friend inline std::ostream& operator<<(std::ostream& os, const IDisplay& rhs).

Implements qpp::IDisplay.

7.22.2.2 operator=()

7.22.3 Member Data Documentation

```
7.22.3.1 end
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::end_ [private]
7.22.3.2 first_
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::first_ [private]
7.22.3.3 last_
template<typename InputIterator>
InputIterator qpp::internal::IOManipRange< InputIterator >::last_ [private]
7.22.3.4 separator_
template<typename InputIterator>
std::string qpp::internal::IOManipRange< InputIterator >::separator_ [private]
7.22.3.5 start_
```

The documentation for this class was generated from the following file:

std::string qpp::internal::IOManipRange< InputIterator >::start_ [private]

• internal/classes/iomanip.h


template<typename InputIterator>

7.23 qpp::is_complex< T > Struct Template Reference


Checks whether the type is a complex type.

#include <traits.h>

Inheritance diagram for qpp::is_complex< T >:



Collaboration diagram for qpp::is_complex< T >:



7.23.1 Detailed Description

template<typename T> struct qpp::is_complex< T>

Checks whether the type is a complex type.

Provides the constant member *value* which is equal to *true*, if the type is a complex type, i.e. *std::complex<T>*

The documentation for this struct was generated from the following file:


· traits.h

7.24 qpp::is_complex < std::complex < T > > Struct Template Reference


Checks whether the type is a complex number type, specialization for complex types.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_complex < std::complex < T > :



Collaboration diagram for qpp::is_complex< std::complex< T >>:



7.24.1 Detailed Description

```
template<typename T> struct qpp::is_complex< std::complex< T>>
```

Checks whether the type is a complex number type, specialization for complex types.

The documentation for this struct was generated from the following file:


traits.h

7.25 qpp::is_iterable < T, typename > Struct Template Reference


Checks whether T is compatible with an STL-like iterable container.

#include <traits.h>

Inheritance diagram for qpp::is_iterable < T, typename >:



Collaboration diagram for qpp::is_iterable < T, typename >:



7.25.1 Detailed Description

template<typename T, typename = void> struct qpp::is_iterable< T, typename >

Checks whether T is compatible with an STL-like iterable container.

Provides the constant member *value* which is equal to *true*, if *T* is compatible with an iterable container, i.e. provides at least *begin()* and *end()* member functions. Otherwise, *value* is equal to *false*.


The documentation for this struct was generated from the following file:

traits.h


Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_iterable < T, to_void < decltype(std::declval < T >().begin()), decltype(std::declval < T >().end()), typename T::value_type > >:



Collaboration diagram for qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval< T >().begin()), typename T::value_type > >:



7.26.1 Detailed Description

```
template < typename \ T > \\ struct \ qpp::is\_iterable < \ T, \ to\_void < \ decltype(std::declval < \ T > ().begin()), \ decltype(std::declval < \ T > ().end()), \ typename \ T \leftarrow \\ ::value\_type > >
```

Checks whether *T* is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

The documentation for this struct was generated from the following file:


· traits.h

7.27 qpp::is_matrix_expression < Derived > Struct Template Reference

Checks whether the type is an Eigen matrix expression.

```
#include <traits.h>
```

Inheritance diagram for qpp::is_matrix_expression< Derived >:



Collaboration diagram for qpp::is matrix expression< Derived >:

```
std::is_base_of< Eigen
::MatrixBase< std::decay
< Derived >::type >, std
::decay< Derived >::type >
```

7.27.1 Detailed Description

```
template < typename Derived > struct qpp::is_matrix_expression < Derived >
```

Checks whether the type is an Eigen matrix expression.

Provides the constant member *value* which is equal to *true*, if the type is an Eigen matrix expression of type *Eigen ∷MatrixBase Oerived* . Otherwise, *value* is equal to *false*.

The documentation for this struct was generated from the following file:


· traits.h

7.28 qpp::QCircuitDescription::iterator Class Reference

Quantum circuit description bound-checking (safe) iterator.

```
#include <classes/circuits.h>
```

Collaboration diagram for qpp::QCircuitDescription::iterator:



Classes

• struct value_type_

Public Types

- using difference_type = long long iterator trait
- using value_type = value_type_

iterator trait

using pointer = const value_type *

iterator trait

using reference = const value_type & iterator trait

• using iterator_category = std::forward_iterator_tag

iterator trait

Public Member Functions

• iterator ()=default

Default constructor.

• iterator (const iterator &)=default

Default copy constructor.

iterator & operator= (const iterator &)=default

Default copy assignment operator.

• iterator & operator++ ()

Prefix increment operator.

iterator operator++ (int)

Postfix increment operator.

• bool operator== (const iterator &rhs) const

Equality operator.

bool operator!= (iterator rhs) const

Inequality operator.

• const value_type_ & operator* () const

Safe dereferencing operator.

Private Member Functions

void set_ (const QCircuitDescription *qcd)

Sets the internal quantum circuit description pointer.

Private Attributes

- · friend QCircuitDescription
- const QCircuitDescription * qcd_ {nullptr}

iterator value type

value_type_ elem_ {nullptr}

de-referenced iterator element

Friends

· class QCircuit

non-owning pointer to const circuit description

7.28.1 Detailed Description

Quantum circuit description bound-checking (safe) iterator.

Note

The iterator is a const_iterator by default

7.28.2 Member Typedef Documentation

```
7.28.2.1 difference_type
using qpp::QCircuitDescription::iterator::difference_type = long long
iterator trait
7.28.2.2 iterator_category
using qpp::QCircuitDescription::iterator:category = std::forward_iterator_tag
iterator trait
7.28.2.3 pointer
using qpp::QCircuitDescription::iterator::pointer = const value_type*
iterator trait
7.28.2.4 reference
using qpp::QCircuitDescription::iterator::reference = const value_type&
iterator trait
7.28.2.5 value_type
using qpp::QCircuitDescription::iterator::value_type = value_type_
iterator trait
7.28.3 Constructor & Destructor Documentation
7.28.3.1 iterator() [1/2]
qpp::QCircuitDescription::iterator::iterator ( ) [default]
Default constructor.
```

```
7.28.3.2 iterator() [2/2]
```

Default copy constructor.

7.28.4 Member Function Documentation

```
7.28.4.1 operator"!=()
```

Inequality operator.

Parameters

rhs | Iterator against which the inequality is being tested

Returns

True if the iterators are not equal (bit by bit), false otherwise

```
7.28.4.2 operator*()
```

```
const value_type_& qpp::QCircuitDescription::iterator::operator* ( ) const [inline]
```

Safe dereferencing operator.

Returns

Constant reference to the iterator element

```
7.28.4.3 operator++() [1/2]
```

```
iterator& qpp::QCircuitDescription::iterator::operator++ ( ) [inline]
```

Prefix increment operator.

Returns

Reference to the current instance

```
7.28.4.4 operator++() [2/2]
```

Postfix increment operator.

Returns

Copy of the current instance before the increment

7.28.4.5 operator=()

Default copy assignment operator.

Returns

Reference to the current instance

7.28.4.6 operator==()

Equality operator.

Parameters

rhs | Iterator against which the equality is being tested

Returns

True if the iterators are equal, false otherwise

```
7.28.4.7 set_()
```

Sets the internal quantum circuit description pointer.

Parameters

qcd | Constant pointer to a quantum circuit description

7.28.5 Friends And Related Function Documentation

7.28.5.1 QCircuit

```
friend class QCircuit [friend]
```

non-owning pointer to const circuit description

7.28.6 Member Data Documentation

```
7.28.6.1 elem_
```

```
value_type_ qpp::QCircuitDescription::iterator::elem_ {nullptr} [private]
```

de-referenced iterator element

7.28.6.2 qcd_

```
const QCircuitDescription* qpp::QCircuitDescription::iterator::qcd_ {nullptr} [private]
```

iterator value type

7.28.6.3 QCircuitDescription

```
friend qpp::QCircuitDescription::iterator::QCircuitDescription [private]
```

The documentation for this class was generated from the following file:

· classes/circuits.h

7.29 qpp::make_void < Ts > Struct Template Reference

Helper for qpp::to_void<> alias template.

```
#include <traits.h>
```

Public Types

• typedef void type

7.29.1 Detailed Description

```
template<typename... Ts>
struct qpp::make_void< Ts>
```

Helper for qpp::to_void<>> alias template.

See also

qpp::to_void<>

7.29.2 Member Typedef Documentation

7.29.2.1 type

```
template<typename... Ts>
typedef void qpp::make_void< Ts >::type
```

The documentation for this struct was generated from the following file:


· traits.h

7.30 qpp::exception::MatrixMismatchSubsys Class Reference


Matrix mismatch subsystems exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixMismatchSubsys:



Collaboration diagram for qpp::exception::MatrixMismatchSubsys:



Public Member Functions

std::string type_description () const override
 Exception type description.

7.30.1 Detailed Description

Matrix mismatch subsystems exception.

Matrix size mismatch subsystem sizes (e.g. in qpp::apply())

7.30.2 Member Function Documentation

7.30.2.1 type_description()

std::string qpp::exception::MatrixMismatchSubsys::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


• classes/exception.h

7.31 qpp::exception::MatrixNotCvector Class Reference


Matrix is not a column vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotCvector:



Collaboration diagram for qpp::exception::MatrixNotCvector:



Public Member Functions

• std::string type_description () const override Exception type description.

7.31.1 Detailed Description

Matrix is not a column vector exception.

Eigen::Matrix is not a column vector

7.31.2 Member Function Documentation

7.31.2.1 type_description()

std::string qpp::exception::MatrixNotCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.32 qpp::exception::MatrixNotRvector Class Reference


Matrix is not a row vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotRvector:



Collaboration diagram for qpp::exception::MatrixNotRvector:



Public Member Functions

std::string type_description () const override
 Exception type description.

7.32.1 Detailed Description

Matrix is not a row vector exception.

Eigen::Matrix is not a row vector

7.32.2 Member Function Documentation

7.32.2.1 type_description()

std::string qpp::exception::MatrixNotRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.33 qpp::exception::MatrixNotSquare Class Reference


Matrix is not square exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquare:



Collaboration diagram for qpp::exception::MatrixNotSquare:



Public Member Functions

std::string type_description () const override
 Exception type description.

7.33.1 Detailed Description

Matrix is not square exception.

Eigen::Matrix is not a square matrix

7.33.2 Member Function Documentation

7.33.2.1 type_description()

std::string qpp::exception::MatrixNotSquare::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.34 qpp::exception::MatrixNotSquareNorCvector Class Reference


Matrix is not square nor column vector exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::MatrixNotSquareNorCvector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorCvector:



Public Member Functions

std::string type_description () const override
 Exception type description.

7.34.1 Detailed Description

Matrix is not square nor column vector exception.

Eigen::Matrix is not a square matrix nor a column vector

7.34.2 Member Function Documentation

7.34.2.1 type_description()

```
std::string qpp::exception::MatrixNotSquareNorCvector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.35 qpp::exception::MatrixNotSquareNorRvector Class Reference


Matrix is not square nor row vector exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::MatrixNotSquareNorRvector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorRvector:



Public Member Functions

std::string type_description () const override
 Exception type description.

7.35.1 Detailed Description

Matrix is not square nor row vector exception.

Eigen::Matrix is not a square matrix nor a row vector

7.35.2 Member Function Documentation

7.35.2.1 type_description()

```
std::string qpp::exception::MatrixNotSquareNorRvector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.36 qpp::exception::MatrixNotSquareNorVector Class Reference


Matrix is not square nor vector exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::MatrixNotSquareNorVector:



Collaboration diagram for qpp::exception::MatrixNotSquareNorVector:



Public Member Functions

std::string type_description () const override
 Exception type description.

7.36.1 Detailed Description

Matrix is not square nor vector exception.

Eigen::Matrix is not a square matrix nor a row/column vector

7.36.2 Member Function Documentation

7.36.2.1 type_description()

```
std::string qpp::exception::MatrixNotSquareNorVector::type_description ( ) const [inline],
[override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.37 qpp::exception::MatrixNotVector Class Reference


Matrix is not a vector exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::MatrixNotVector:



Collaboration diagram for qpp::exception::MatrixNotVector:



Public Member Functions

std::string type_description () const override
 Exception type description.

7.37.1 Detailed Description

Matrix is not a vector exception.

Eigen::Matrix is not a row or column vector

7.37.2 Member Function Documentation

7.37.2.1 type_description()

std::string qpp::exception::MatrixNotVector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.


The documentation for this class was generated from the following file:

· classes/exception.h

7.38 qpp::QCircuitDescription::MeasureStep Struct Reference

One step consisting only of measurements in the circuit.

Collaboration diagram for qpp::QCircuitDescription::MeasureStep:



Public Member Functions

• MeasureStep ()=default

Default constructor.

MeasureStep (MeasureType measurement_type, const std::vector < cmat > &mats, const std::vector < idx > &target, idx c_reg, idx step_no, std::string name="")

Constructs a measurement step instance.

Public Attributes

```
    MeasureType measurement_type_ = MeasureType::NONE
```

measurement type

- std::vector< cmat > mats_
- std::vector < idx > target_

measurement

idx c_reg_ {}

result is being stored

idx step_no_

step number

· std::string name_

custom name of the step

7.38.1 Detailed Description

One step consisting only of measurements in the circuit.

7.38.2 Constructor & Destructor Documentation

```
7.38.2.1 MeasureStep() [1/2]
```

```
\verb"qpp::QCircuitDescription::MeasureStep::MeasureStep" ( ) \  \  [default]
```

Default constructor.

7.38.2.2 MeasureStep() [2/2]

Constructs a measurement step instance.

Parameters

measurement_type	Measurement type
mats	Vector of measurement matrices (can be only one or many for Kraus measurements)
target	Target qudit indexes
c_reg	Classical register where the value of the measurement is stored
step_no	Circuit step number
G ମ୍ମୟମୀତ d by Doxygen	Optional gate name

7.38.3 Member Data Documentation

```
7.38.3.1 c_reg_
idx qpp::QCircuitDescription::MeasureStep::c_reg_ {}
result is being stored
index of the classical register where the measurement
7.38.3.2 mats_
std::vector<cmat> qpp::QCircuitDescription::MeasureStep::mats_
matrix/matrices that specify the
7.38.3.3 measurement_type_
MeasureType qpp::QCircuitDescription::MeasureStep::measurement_type_ = MeasureType::NONE
measurement type
7.38.3.4 name_
std::string qpp::QCircuitDescription::MeasureStep::name_
custom name of the step
7.38.3.5 step_no_
idx qpp::QCircuitDescription::MeasureStep::step_no_
step number
```

7.38.3.6 target_

std::vector<idx> qpp::QCircuitDescription::MeasureStep::target_

measurement

target where the measurement is applied

The documentation for this struct was generated from the following file:


· classes/circuits.h

7.39 qpp::exception::NoCodeword Class Reference


Codeword does not exist exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NoCodeword:



Collaboration diagram for qpp::exception::NoCodeword:



Public Member Functions

std::string type_description () const override
 Exception type description.

7.39.1 Detailed Description

Codeword does not exist exception.

Codeword does not exist, thrown when calling qpp::Codes::codeword() with an invalid index

7.39.2 Member Function Documentation

7.39.2.1 type_description()

std::string qpp::exception::NoCodeword::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.40 qpp::exception::NotBipartite Class Reference


Not bi-partite exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotBipartite:



Collaboration diagram for qpp::exception::NotBipartite:



Public Member Functions

• std::string type_description () const override Exception type description.

7.40.1 Detailed Description

Not bi-partite exception.

std::vector<idx> of dimensions has size different from 2

7.40.2 Member Function Documentation

7.40.2.1 type_description()

std::string qpp::exception::NotBipartite::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.41 qpp::exception::NotImplemented Class Reference


Code not yet implemented.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotImplemented:



Collaboration diagram for qpp::exception::NotImplemented:



Public Member Functions

• std::string type_description () const override Exception type description.

7.41.1 Detailed Description

Code not yet implemented.

7.41.2 Member Function Documentation

7.41.2.1 type_description()

std::string qpp::exception::NotImplemented::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.42 qpp::exception::NotQubitCvector Class Reference


Column vector is not 2 x 1 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitCvector:



Collaboration diagram for qpp::exception::NotQubitCvector:



Public Member Functions

std::string type_description () const override
 Exception type description.

7.42.1 Detailed Description

Column vector is not 2 x 1 exception.

Eigen::Matrix is not 2 x 1

7.42.2 Member Function Documentation

7.42.2.1 type_description()

std::string qpp::exception::NotQubitCvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


• classes/exception.h

7.43 qpp::exception::NotQubitMatrix Class Reference


Matrix is not 2 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitMatrix:



Collaboration diagram for qpp::exception::NotQubitMatrix:



Public Member Functions

• std::string type_description () const override Exception type description.

7.43.1 Detailed Description

Matrix is not 2 x 2 exception.

Eigen::Matrix is not 2 x 2

7.43.2 Member Function Documentation

7.43.2.1 type_description()

std::string qpp::exception::NotQubitMatrix::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.44 qpp::exception::NotQubitRvector Class Reference


Row vector is not 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitRvector:



Collaboration diagram for qpp::exception::NotQubitRvector:



Public Member Functions

std::string type_description () const override
 Exception type description.

7.44.1 Detailed Description

Row vector is not 1 x 2 exception.

Eigen::Matrix is not 1 x 2

7.44.2 Member Function Documentation

7.44.2.1 type_description()

std::string qpp::exception::NotQubitRvector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.45 qpp::exception::NotQubitSubsys Class Reference


Subsystems are not qubits exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitSubsys:



Collaboration diagram for qpp::exception::NotQubitSubsys:



Public Member Functions

std::string type_description () const override
 Exception type description.

7.45.1 Detailed Description

Subsystems are not qubits exception.

Subsystems are not 2-dimensional (qubits)

7.45.2 Member Function Documentation

7.45.2.1 type_description()

std::string qpp::exception::NotQubitSubsys::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.46 qpp::exception::NotQubitVector Class Reference


Vector is not 2 x 1 nor 1 x 2 exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::NotQubitVector:



Collaboration diagram for qpp::exception::NotQubitVector:



Public Member Functions

std::string type_description () const override
 Exception type description.

7.46.1 Detailed Description

Vector is not 2 x 1 nor 1 x 2 exception.

Eigen::Matrix is not 2 x 1 nor 1 x 2

7.46.2 Member Function Documentation

7.46.2.1 type_description()

std::string qpp::exception::NotQubitVector::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.47 qpp::exception::OutOfRange Class Reference


Argument out of range exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::OutOfRange:



Collaboration diagram for qpp::exception::OutOfRange:



Public Member Functions

• std::string type_description () const override Exception type description.

7.47.1 Detailed Description

Argument out of range exception.

Argument out of range

7.47.2 Member Function Documentation

7.47.2.1 type_description()

std::string qpp::exception::OutOfRange::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


• classes/exception.h

7.48 qpp::exception::PermInvalid Class Reference


Invalid permutation exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermInvalid:



Collaboration diagram for qpp::exception::PermInvalid:



Public Member Functions

• std::string type_description () const override Exception type description.

7.48.1 Detailed Description

Invalid permutation exception.

std::vector<idx> does note represent a valid permutation

7.48.2 Member Function Documentation

7.48.2.1 type_description()

std::string qpp::exception::PermInvalid::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.49 qpp::exception::PermMismatchDims Class Reference


Permutation mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::PermMismatchDims:



Collaboration diagram for qpp::exception::PermMismatchDims:



Public Member Functions

std::string type_description () const override
 Exception type description.

7.49.1 Detailed Description

Permutation mismatch dimensions exception.

Size of the std::vector<idx> representing the permutation is different from the size of the std::vector<idx> of dimensions

7.49.2 Member Function Documentation

7.49.2.1 type_description()

std::string qpp::exception::PermMismatchDims::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.50 qpp::QCircuit Class Reference


Quantum circuit simulator class.

#include <classes/circuits.h>

Inheritance diagram for qpp::QCircuit:



Collaboration diagram for qpp::QCircuit:



Public Member Functions

QCircuit (const QCircuitDescription &qcd)

Constructs a quantum circuit out of a quantum circuit description.

QCircuit (QCircuitDescription &&)=delete

Disables rvalue QCircuitDescription.

· ket get_psi () const

Underlying quantum state.

std::vector< idx > get_dits () const

Vector with the values of the underlying classical dits.

• idx get_dit (idx i) const

Value of the classical dit at position i.

std::vector< double > get_probs () const

Vector of underlying measurement outcome probabilities.

· idx get measured (idx i) const

Check whether qudit i was already measured.

std::vector< idx > get_measured () const

Vector of already measured qudit indexes.

std::vector< idx > get_not_measured () const

Vector of non-measured qudit indexes.

bool is_measurement_step () const

Checks whether the current step in the circuit is a measurement step.

idx get_m_ip () const

Measurement instruction pointer.

idx get_q_ip () const

Quantum instruction pointer.

• idx get_ip () const

Total instruction pointer.

• QCircuitDescription::const_iterator get_iter () const

Iterator to current step.

const QCircuitDescription & get_circuit_description () const

Quantum circuit description.

QCircuit & set_dit (idx i, idx value)

Sets the classical dit at position i.

• void reset ()

Resets the quantum circuit.

void run (bool verbose=false, idx step=idx_infty)

Executes the quantum circuit.

std::ostream & display (std::ostream &os) const override

qpp::IDisplay::display() override

Protected Member Functions

void set_measured_ (idx i)

Marks qudit i as measured then re-label accordingly the remaining non-measured qudits.

std::vector< idx > get_relative_pos_ (std::vector< idx > v)

Giving a vector V of non-measured qudits, get their relative position with respect to the measured qudits.

Protected Attributes

```
    const QCircuitDescription & qcd_
quantum circuit description
```

ket psi_

state vector

std::vector< idx > dits_

classical dits

std::vector< double > probs_

measurement probabilities

std::vector< idx > subsys_

relabel them after measurements

· QCircuitDescription::const_iterator it_

iterator to current step

7.50.1 Detailed Description

Quantum circuit simulator class.

See also

qpp::QCircuitDescription

7.50.2 Constructor & Destructor Documentation

Constructs a quantum circuit out of a quantum circuit description.

Note

the quantum circuit description must be an Ivalue

See also

qpp::QCircuit(QCircuitDescription&&)

Note

The initial underlying quantum state is set to $|0\rangle^{\otimes n}$

Parameters

qcd Quantum circuit description

```
7.50.2.2 QCircuit() [2/2]
```

Disables rvalue QCircuitDescription.

7.50.3 Member Function Documentation

```
7.50.3.1 display()
```

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the quantum circuit

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.50.3.2 get_circuit_description()

```
\verb|const QCircuitDescription@| qpp::QCircuit::get\_circuit\_description () const [inline]|
```

Quantum circuit description.

Returns

Quantum circuit description

7.50.3.3 get_dit()

```
idx qpp::QCircuit::get_dit (
        idx i) const [inline]
```

Value of the classical dit at position i.

Parameters

```
i Classical dit index
```

Returns

Value of the classical dit at position i

```
7.50.3.4 get_dits()
```

```
std::vector<idx> qpp::QCircuit::get_dits ( ) const [inline]
```

Vector with the values of the underlying classical dits.

Returns

Vector of underlying classical dits

```
7.50.3.5 get_ip()
```

```
idx qpp::QCircuit::get_ip ( ) const [inline]
```

Total instruction pointer.

Returns

The sum of measurement instruction pointer and quantum instruction pointer

7.50.3.6 get_iter()

```
QCircuitDescription::const_iterator qpp::QCircuit::get_iter ( ) const [inline]
```

Iterator to current step.

Returns

Iterator to current step in the circuit

```
7.50.3.7 get_m_ip()
```

```
idx qpp::QCircuit::get_m_ip ( ) const [inline]
```

Measurement instruction pointer.

Points to the index of the next measurement to be executed from the std::vector<MeasureStep> of measurements in the circuit description

Returns

Measurement instruction pointer

7.50.3.8 get_measured() [1/2]

Check whether qudit i was already measured.

Parameters

```
i Qudit index
```

Returns

True if qudit *i* was already measured, false othwewise

```
7.50.3.9 get_measured() [2/2]
```

```
std::vector<idx> qpp::QCircuit::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

7.50.3.10 get_not_measured()

```
std::vector<idx> qpp::QCircuit::get_not_measured ( ) const [inline]
```

Vector of non-measured qudit indexes.

Returns

Vector of non-measured qudit indexes

7.50.3.11 get_probs()

```
std::vector<double> qpp::QCircuit::get_probs ( ) const [inline]
```

Vector of underlying measurement outcome probabilities.

Note

The probability vector has the same length as the vector of classical dits. If the measurement result is stored at the index c_reg , then the outcome probability is automatically stored at the same index c_reg in the probability vector.

Returns

Vector of underlying measurement outcome probabilities

```
7.50.3.12 get_psi()
```

```
ket qpp::QCircuit::get_psi ( ) const [inline]
```

Underlying quantum state.

Returns

Underlying quantum state

7.50.3.13 get_q_ip()

```
idx qpp::QCircuit::get_q_ip ( ) const [inline]
```

Quantum instruction pointer.

Points to the index of the next quantum gate to be executed from the std::vector<GateStep> of quantum gates in the circuit description

Returns

Quantum instruction pointer

7.50.3.14 get_relative_pos_()

```
\label{eq:condition} $$ std::vector < idx> qpp::QCircuit::get_relative_pos_ ( std::vector < idx> v ) [inline], [protected]
```

Giving a vector *V* of non-measured qudits, get their relative position with respect to the measured qudits.

Parameters

```
v Qudit index
```

7.50.3.15 is_measurement_step()

```
bool qpp::QCircuit::is_measurement_step ( ) const [inline]
```

Checks whether the current step in the circuit is a measurement step.

Returns

True if measurement step, false otherwise

7.50.3.16 reset()

```
void qpp::QCircuit::reset ( ) [inline]
```

Resets the quantum circuit.

Re-initializes everything to zero and sets the initial state to $|0\rangle^{\otimes n}$

7.50.3.17 run()

Executes the quantum circuit.

Parameters

	step	How many steps to execute, by default executes until the end	
1	verbose	If true, displays at console every executed step	1

7.50.3.18 set_dit()

Sets the classical dit at position i.

Parameters

i	Classical dit index
value	Classical dit value

Returns

Reference to the current instance

```
7.50.3.19 set_measured_()
```

Marks qudit *i* as measured then re-label accordingly the remaining non-measured qudits.

Parameters

i Qudit index

7.50.4 Member Data Documentation

```
7.50.4.1 dits_
std::vector<idx> qpp::QCircuit::dits_ [protected]
classical dits
```

```
7.50.4.2 it_
```

```
QCircuitDescription::const_iterator qpp::QCircuit::it_ [protected]
```

iterator to current step

```
7.50.4.3 probs_
std::vector<double> qpp::QCircuit::probs_ [protected]
measurement probabilities
```

```
7.50.4.4 psi_
ket qpp::QCircuit::psi_ [protected]
state vector

7.50.4.5 qcd_
const QCircuitDescription@ qpp::QCircuit::qcd_ [protected]
quantum circuit description
```

```
7.50.4.6 subsys_
```

std::vector<idx> qpp::QCircuit::subsys_ [protected]

relabel them after measurements

keeps track of the measured subsystems,

The documentation for this class was generated from the following file:


· classes/circuits.h

7.51 qpp::QCircuitDescription Class Reference


Quantum circuit description class.

```
#include <classes/circuits.h>
```

Inheritance diagram for qpp::QCircuitDescription:



Collaboration diagram for qpp::QCircuitDescription:



Classes

struct GateStep

One step consisting only of gates/operators in the circuit.

· class iterator

Quantum circuit description bound-checking (safe) iterator.

struct MeasureStep

One step consisting only of measurements in the circuit.

Public Types

enum GateType {

GateType::NONE, GateType::SINGLE, GateType::TWO, GateType::THREE,
GateType::CUSTOM, GateType::FAN, GateType::QFT, GateType::TFQ,
GateType::SINGLE_CTRL_SINGLE_TARGET, GateType::SINGLE_CTRL_MULTIPLE_TARGET, Gate
Type::MULTIPLE_CTRL_SINGLE_TARGET, GateType::MULTIPLE_CTRL_MULTIPLE_TARGET,
GateType::CUSTOM_CTRL, GateType::SINGLE_cCTRL_SINGLE_TARGET, GateType::SINGLE_cCTRL
_MULTIPLE_TARGET, GateType::MULTIPLE_cCTRL_SINGLE_TARGET,
GateType::MULTIPLE cCTRL MULTIPLE TARGET, GateType::CUSTOM cCTRL }

Type of gate being executed in a gate step.

 enum MeasureType { MeasureType::MEASURE_Z, MeasureType::MEASURE_V, MeasureType::MEASURE_V_MANY }

Type of measurement being executed in a measurement step.

• using const_iterator = iterator

both iterators are const_iterators

Public Member Functions

• iterator begin ()

Iterator to the first element.

· const_iterator begin () const noexcept

Constant iterator to the first element.

const_iterator cbegin () const noexcept

Constant iterator to the first element.

· iterator end ()

Iterator to the next to the last element.

const_iterator end () const noexcept

Constant iterator to the next to the last element.

· const_iterator cend () const noexcept

Constant iterator to the next to the last element.

QCircuitDescription (idx nq, idx nc=0, idx d=2, std::string name="")

Constructs a quantum circuit description.

• idx get ng () const noexcept

Total number of qudits in the circuit.

idx get_nc () const noexcept

Total number of classical dits in the circuit.

• idx get d () const noexcept

Local dimension of the comprising qudits.

std::vector< idx > get_measurement_steps () const

Vector of measurement positions in the circuit, i.e. the indexes where the measurements take place.

const std::vector< MeasureStep > & get measurements () const noexcept

Vector of qpp::QCircuitDescription::MeasureStep.

const std::vector< GateStep > & get_gates () const noexcept

Vector of qpp::QCircuitDescription::GateStep.

• std::string get_name () const

Quantum circuit name.

• idx get_measured (idx i) const

Check whether qudit i was already measured.

std::vector < idx > get measured () const

Vector of already measured qudit indexes.

std::vector< idx > get_non_measured () const

Vector of non-measured qudit indexes.

idx get_gate_count () const noexcept

Quantum circuit total gate count.

• idx get_measurement_count () const noexcept

Quantum circuit total measurement count.

idx get_steps_count () const noexcept

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

QCircuitDescription & gate (const cmat &U, idx i, std::string name="")

Applies the single qudit gate U on single qudit i.

QCircuitDescription & gate (const cmat &U, idx i, idx j, std::string name="")

Applies the two qudit gate U on qudits i and j.

QCircuitDescription & gate (const cmat &U, idx i, idx j, idx k, std::string name="")

Applies the three qudit gate U on qudits i, j and k.

QCircuitDescription & gate_fan (const cmat &U, const std::vector < idx > &target, std::string name="")

Applies the single qudit gate U on every qudit listed in target.

• QCircuitDescription & gate fan (const cmat &U, std::string name="")

Applies the single qudit gate U on every remaining non-measured qudit.

QCircuitDescription & gate_custom (const cmat &U, const std::vector< idx > &target, std::string name="")

Jointly applies the custom multiple qudit gate U on the qudit indexes specified by target.

QCircuitDescription & QFT (const std::vector < idx > &target, bool swap QPP UNUSED =true)

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuitDescription & TFQ (const std::vector < idx > &target, bool swap QPP_UNUSED_=true)

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

QCircuitDescription & CTRL (const cmat &U, idx ctrl, idx target, std::string name="")

Applies the single qudit controlled gate U with control qudit ctrl and target qudit target.

QCircuitDescription & CTRL (const cmat &U, idx ctrl, const std::vector< idx > &target, std::string name=""")

Applies the single qudit controlled gate U with control qudit ctrl on every qudit listed in target.

QCircuitDescription & CTRL (const cmat &U, const std::vector < idx > &ctrl, idx target, std::string name=""")

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on the target qudit target.

QCircuitDescription & CTRL (const cmat &U, const std::vector < idx > &ctrl, const std::vector < idx > &target, std::string name="")

Applies the single qudit controlled gate U with multiple control qudits listed in ctrl on every qudit listed in target.

QCircuitDescription & CTRL_custom (const cmat &U, const std::vector< idx > &ctrl, const std::vector< idx > &target, std::string name="")

Jointly applies the custom multiple-qudit controlled gate U with multiple control qudits listed in ctrl on the qudit indexes specified by target.

QCircuitDescription & cCTRL (const cmat &U, idx ctrl_dit, idx target, std::string name="")

Applies the single qubit controlled gate U with classical control dit ctrl and target qudit target.

QCircuitDescription & cCTRL (const cmat &U, idx ctrl_dit, const std::vector< idx > &target, std::string name="")

Applies the single qudit controlled gate U with classical control dit ctrl on every qudit listed in target.

QCircuitDescription & cCTRL (const cmat &U, const std::vector< idx > &ctrl_dits, idx target, std::string name="")

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on the target qudit target.

QCircuitDescription & cCTRL (const cmat &U, const std::vector< idx > &ctrl_dits, const std::vector< idx > &target, std::string name="")

Applies the single qudit controlled gate U with multiple classical control dits listed in ctrl on every qudit listed in target.

QCircuitDescription & cCTRL_custom (const cmat &U, const std::vector < idx > &ctrl_dits, const std::vector < idx > &target, std::string name="")

Jointly applies the custom multiple-qudit controlled gate U with multiple classical control dits listed in ctrl on the qudit indexes specified by target.

QCircuitDescription & measureZ (idx i, idx c_reg, std::string name="")

Measurement of single qudit in the computational basis (Z-basis)

QCircuitDescription & measureV (const cmat &V, idx i, idx c_reg, std::string name="")

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

QCircuitDescription & measureV (const cmat &V, const std::vector< idx > &target, idx c_reg, std::string name="")

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

• std::ostream & display (std::ostream &os) const override

qpp::IDisplay::display() override

• std::string to_JSON () const

Protected Member Functions

std::string _to_JSON () const

Private Attributes

const idx nq

number of qudits

const idx nc_

number of classical "dits"

const idx d

dimension

std::vector< idx > measurement_steps_{}{}

measurements take place

Friends

- std::ostream & operator << (std::ostream &os, const GateType &gate_type)

 Extraction operator overload for qpp::QCircuitDescription::GateType enum class.
- std::ostream & operator << (std::ostream &os, const MeasureType &measure_type)

 Extraction operator overload for qpp::QCircuitDescription::MeasureType enum class.
- std::ostream & operator<< (std::ostream &os, const GateStep &gate_step)

 Extraction operator overload for qpp::QCircuitDescription::GateStep class.
- std::ostream & operator << (std::ostream &os, const MeasureStep &measure_step) Extraction operator overload for qpp::QCircuitDescription::MeasureStep class.

7.51.1 Detailed Description

Quantum circuit description class.

See also

qpp::QCircuit

7.51.2 Member Typedef Documentation

```
7.51.2.1 const_iterator

using qpp::QCircuitDescription::const_iterator = iterator

both iterators are const iterators
```

7.51.3 Member Enumeration Documentation

```
7.51.3.1 GateType
enum qpp::QCircuitDescription::GateType [strong]
```

Type of gate being executed in a gate step.

Enumerator

NONE	represents no gate
SINGLE	unitary gate on a single qudit
TWO	unitary gate on 2 qudits
THREE	unitary gate on 3 qudits
CUSTOM	custom gate on multiple qudits
FAN	same unitary gate on multiple qudits
QFT	quantum Fourier transform,
TFQ	quantum inverse Fourier transform,
SINGLE_CTRL_SINGLE_TARGET	one control and one target controlled 1 qudit unitary gate with
SINGLE_CTRL_MULTIPLE_TARGET	one control and multiple targets controlled 1 qudit unitary gate with
MULTIPLE_CTRL_SINGLE_TARGET	multiple controls and single target controlled 1 qudit unitary gate with
MULTIPLE_CTRL_MULTIPLE_TARGET	multiple controls and multiple targets controlled 1 qudit unitary gate with
CUSTOM_CTRL	and multiple targets custom controlled gate with multiple controls
SINGLE_cCTRL_SINGLE_TARGET	one classical control and one target controlled 1 qudit unitary gate with
SINGLE_cCTRL_MULTIPLE_TARGET	one classical control and multiple targets controlled 1 qudit unitary gate with
MULTIPLE_cCTRL_SINGLE_TARGET	multiple classical controls and single target controlled 1 qudit unitary gate with
MULTIPLE_cCTRL_MULTIPLE_TARGET	with multiple classical controls and multiple targets controlled 1 qudit unitary gate
CUSTOM_cCTRL	multiple targets custom controlled gate with multiple controls and

7.51.3.2 MeasureType

enum qpp::QCircuitDescription::MeasureType [strong]

Type of measurement being executed in a measurement step.

Enumerator

NONE	represents no measurement
MEASURE_Z	Z measurement of single qudit.
MEASURE_V	or rank-1 projectors specified by the columns of matrix V measurement of single qudit in the orthonormal basis
MEASURE_V_MANY	basis or rank-1 projectors specified by the columns of matrix V measurement of multiple qudits in the orthonormal

7.51.4 Constructor & Destructor Documentation

7.51.4.1 QCircuitDescription()

```
qpp::QCircuitDescription::QCircuitDescription (
    idx nq,
    idx nc = 0,
    idx d = 2,
    std::string name = "" ) [inline], [explicit]
```

Constructs a quantum circuit description.

Note

The measurement results can only be stored in the classical dits of which number is specified by nc

Parameters

nq	Number of qbits
nc	Number of classical dits
d Subsystem dimensions (optional, default is qubit, i.e. $d = 2$	
name	Circuit description name (optional)

7.51.5 Member Function Documentation

```
7.51.5.1 _to_JSON()
```

```
std::string qpp::QCircuitDescription::_to_JSON ( ) const [inline], [protected]
```

```
7.51.5.2 begin() [1/2]
```

```
iterator qpp::QCircuitDescription::begin ( ) [inline]
```

Iterator to the first element.

Returns

Iterator to the first element

```
7.51.5.3 begin() [2/2]
```

```
const_iterator qpp::QCircuitDescription::begin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

7.51.5.4 cbegin()

```
const_iterator qpp::QCircuitDescription::cbegin ( ) const [inline], [noexcept]
```

Constant iterator to the first element.

Returns

Constant iterator to the first element

```
7.51.5.5 cCTRL() [1/4]
```

Applies the single qubit controlled gate *U* with classical control dit *ctrl* and target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.51.5.6 cCTRL() [2/4]
```

Applies the single qudit controlled gate *U* with classical control dit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl_dit	Classical control dit index
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the
	classical control dits
name	Optional gate name

Returns

Reference to the current instance

```
7.51.5.7 cCTRL() [3/4]
```

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.51.5.8 cCTRL() [4/4]
```

```
const std::vector< idx > & ctrl_dits,
const std::vector< idx > & target,
std::string name = "" ) [inline]
```

Applies the single qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the
	classical control dits
name	Optional gate name

Returns

Reference to the current instance

7.51.5.9 cCTRL_custom()

Jointly applies the custom multiple-qudit controlled gate *U* with multiple classical control dits listed in *ctrl* on the qudit indexes specified by *target*.

Parameters

U	Multiple-qudit quantum gate
ctrl_dits	Classical control dits indexes
target	Target qudit indexes where the gate U is applied depending on the values of the classical control dits
name	Optional gate name

Returns

Reference to the current instance

7.51.5.10 cend()

```
const_iterator qpp::QCircuitDescription::cend ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

Returns

Constant iterator to the next to the last element

Applies the single qudit controlled gate *U* with control qudit *ctrl* and target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.51.5.12 CTRL() [2/4]
```

Applies the single qudit controlled gate *U* with control qudit *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit index
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the target qudit *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.51.5.14 CTRL() [4/4]
```

Applies the single qudit controlled gate *U* with multiple control qudits listed in *ctrl* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes; the gate U is applied on every one of them depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

7.51.5.15 CTRL_custom()

Jointly applies the custom multiple-qudit controlled gate *U* with multiple control qudits listed in *ctrl* on the qudit indexes specified by *target*.

Parameters

U	Multiple-qudit quantum gate
ctrl	Control qudit indexes
target	Target qudit indexes where the gate U is applied depending on the values of the control qudits
name	Optional gate name

Returns

Reference to the current instance

7.51.5.16 display()

qpp::IDisplay::display() override

Writes to the output stream a textual representation of the quantum circuit description

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.51.5.17 end() [1/2]
```

```
iterator qpp::QCircuitDescription::end ( ) [inline]
```

Iterator to the next to the last element.

Returns

Iterator to the next to the last element

```
7.51.5.18 end() [2/2]

const_iterator qpp::QCircuitDescription::end ( ) const [inline], [noexcept]
```

Constant iterator to the next to the last element.

Returns

Constant iterator to the next to the last element

Applies the single qudit gate *U* on single qudit *i*.

Parameters

U	Single qudit quantum gate
i	Qudit index
name	Optional gate name

Returns

Reference to the current instance

```
idx i,
idx j,
std::string name = "" ) [inline]
```

Applies the two qudit gate *U* on qudits *i* and *j*.

Parameters

U	Two qudit quantum gate
i	Qudit index
j	Qudit index
name	Optional gate name

Returns

Reference to the current instance

```
7.51.5.21 gate() [3/3]
```

Applies the three qudit gate U on qudits i, j and k.

Parameters

U	Three qudit quantum gate
i	Qudit index
j	Qudit index
k	Qudit index
name	Optional gate name

Returns

Reference to the current instance

7.51.5.22 gate_custom()

Jointly applies the custom multiple qudit gate *U* on the qudit indexes specified by *target*.

Parameters

U	Multiple qudit quantum gate	
target	Subsystem indexes where the gate U is applied	
name	Optional gate name	

Returns

Reference to the current instance

Applies the single qudit gate *U* on every qudit listed in *target*.

Parameters

U	Single qudit quantum gate
target	Target qudit indexes; the gate <i>U</i> is applied on every one of them
name	Optional gate name

Returns

Reference to the current instance

Applies the single qudit gate $\it U$ on every remaining non-measured qudit.

Parameters

U	Single qudit quantum gate
name	Optional gate name

Returns

Reference to the current instance

```
7.51.5.25 get_d()
idx qpp::QCircuitDescription::get_d ( ) const [inline], [noexcept]
Local dimension of the comprising qudits.
Returns
     Local dimension
7.51.5.26 get_gate_count()
idx qpp::QCircuitDescription::get_gate_count ( ) const [inline], [noexcept]
Quantum circuit total gate count.
Returns
     Total gate count
7.51.5.27 get_gates()
const std::vector<GateStep>& qpp::QCircuitDescription::get_gates ( ) const [inline], [noexcept]
Vector of qpp::QCircuitDescription::GateStep.
Returns
     Vector of qpp::QCircuitDescription::GateStep
7.51.5.28 get_measured() [1/2]
idx qpp::QCircuitDescription::get_measured (
```

Generated by Doxygen

idx i) const [inline]

Check whether qudit *i* was already measured.

Parameters

i Qudit index

Returns

True if qudit i was already measured, false othwewise

```
7.51.5.29 get_measured() [2/2]
std::vector<idx> qpp::QCircuitDescription::get_measured ( ) const [inline]
```

Vector of already measured qudit indexes.

Returns

Vector of already measured qudit indexes

7.51.5.30 get_measurement_count()

```
idx qpp::QCircuitDescription::get_measurement_count ( ) const [inline], [noexcept]
```

Quantum circuit total measurement count.

Returns

Total measurement count

7.51.5.31 get_measurement_steps()

```
std::vector<idx> qpp::QCircuitDescription::get_measurement_steps ( ) const [inline]
```

Vector of measurement positions in the circuit, i.e. the indexes where the measurements take place.

Note

If there are more consecutive measurements after step S, then their indexes will all be S, i.e. it is always assumed that the measurements taking place immediately after a gate step have the same index as the preceding gate step.

Returns

Vector of measurement positions

```
7.51.5.32 get_measurements()
```

```
const std::vector<MeasureStep>& qpp::QCircuitDescription::get_measurements ( ) const [inline],
[noexcept]
```

Vector of qpp::QCircuitDescription::MeasureStep.

Returns

Vector of qpp::QCircuitDescription::MeasureStep

```
7.51.5.33 get_name()
```

```
std::string qpp::QCircuitDescription::get_name ( ) const [inline]
```

Quantum circuit name.

Returns

Quantum circuit name

```
7.51.5.34 get_nc()
```

```
idx qpp::QCircuitDescription::get_nc ( ) const [inline], [noexcept]
```

Total number of classical dits in the circuit.

Returns

Total number of classical dits

```
7.51.5.35 get_non_measured()
```

```
\verb|std::vector<| idx>| qpp::QCircuitDescription::get_non_measured () const [inline]|
```

Vector of non-measured qudit indexes.

Returns

Vector of non-measured qudit indexes

7.51.5.36 get_nq()

```
idx qpp::QCircuitDescription::get_nq ( ) const [inline], [noexcept]
```

Total number of qudits in the circuit.

Returns

Total number of qudits

```
7.51.5.37 get_steps_count()
```

```
idx qpp::QCircuitDescription::get_steps_count ( ) const [inline], [noexcept]
```

Quantum circuit total steps count, i.e. the sum of gate count and measurement count.

Returns

Total (gates + measurements) count

7.51.5.38 measureV() [1/2]

Measurement of single qudit in the orthonormal basis or rank-1 projectors specified by the columns of matrix V.

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V
i	Qudit index
c_reg	Classical register where the value of the measurement is stored
name	Optional measurement name

Returns

Reference to the current instance

7.51.5.39 measureV() [2/2]

Joint measurement of multiple qudits in the orthonormal basis or rank-1 projectors specified by the columns of matrix *V*.

Parameters

V	Orthonormal basis or rank-1 projectors specified by the columns of matrix V
target	Target qudit indexes that are jointly measured
c_reg	Classical register where the value of the measurement is stored
name	Optional measurement name

Returns

Reference to the current instance

7.51.5.40 measureZ()

Measurement of single qudit in the computational basis (Z-basis)

Parameters

i	Qudit index
c_reg	Classical register where the value of the measurement is being stored
name	Optional measurement name, default is "Measure Z"

Returns

Reference to the current instance

7.51.5.41 QFT()

Applies the quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

7.51.5.42 TFQ()

Applies the inverse quantum Fourier transform (as a series of gates) on the qudit indexes specified by target.

Parameters

target	Subsystem indexes where the inverse quantum Fourier transform is applied
swap	Swaps the qubits at the end (true by default)

Returns

Reference to the current instance

```
7.51.5.43 to_JSON()
```

```
std::string qpp::QCircuitDescription::to_JSON ( ) const [inline]
```

7.51.6 Friends And Related Function Documentation

Extraction operator overload for qpp::QCircuitDescription::GateType enum class.

Parameters

os	Output stream
gate_type	qpp::QCircuitDescription::GateType enum class

Returns

Output stream

Extraction operator overload for qpp::QCircuitDescription::MeasureType enum class.

Parameters

os	Output stream
gate_type	qpp::QCircuitDescription::MeasureType enum class

Returns

Output stream

Extraction operator overload for qpp::QCircuitDescription::GateStep class.

Parameters

os	Output stream
gate_type	qpp::QCircuitDescription::GateStep class

Returns

Output stream

Extraction operator overload for qpp::QCircuitDescription::MeasureStep class.

const MeasureStep & measure_step) [friend]

Parameters

os	Output stream
gate_type	qpp::QCircuitDescription::MeasureStep enum class

Returns

Output stream

7.51.7 Member Data Documentation

```
7.51.7.1 d_
const idx qpp::QCircuitDescription::d_ [private]
```

```
7.51.7.2 gates_
```

dimension

```
std::vector<GateStep> qpp::QCircuitDescription::gates_ {} [private]
```

gates

```
7.51.7.3 measured_
```

```
std::vector<bool> qpp::QCircuitDescription::measured_ [private]
```

keeps track of the measured qudits

```
7.51.7.4 measurement_steps_
std::vector<idx> qpp::QCircuitDescription::measurement_steps_ {} [private]
measurements take place
keeps track of where the
7.51.7.5 measurements
std::vector<MeasureStep> qpp::QCircuitDescription::measurements_ {} [private]
measurements
7.51.7.6 name_
std::string qpp::QCircuitDescription::name_ [private]
optional circuit name
7.51.7.7 nc_
const idx qpp::QCircuitDescription::nc_ [private]
number of classical "dits"
7.51.7.8 nq_
const idx qpp::QCircuitDescription::nq_ [private]
number of qudits
7.51.7.9 steps_cnt_
idx qpp::QCircuitDescription::steps_cnt_ [private]
step counter
```

Generated by Doxygen

· classes/circuits.h


The documentation for this class was generated from the following file:

7.52 qpp::exception::QuditAlreadyMeasured Class Reference


Qudit was already measured exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::QuditAlreadyMeasured:



Collaboration diagram for qpp::exception::QuditAlreadyMeasured:



Public Member Functions

std::string type_description () const override
 Exception type description.

7.52.1 Detailed Description

Qudit was already measured exception.

The qudit was already measured and cannot be measured again

7.52.2 Member Function Documentation

7.52.2.1 type_description()

std::string qpp::exception::QuditAlreadyMeasured::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.53 qpp::RandomDevices Class Reference


Singleton class that manages the source of randomness in the library.

```
#include <classes/random_devices.h>
```

Inheritance diagram for qpp::RandomDevices:



Collaboration diagram for qpp::RandomDevices:



Public Member Functions

• std::mt19937 & get_prng ()

Returns a reference to the internal PRNG object.

• std::istream & load (std::istream &is)

Loads the state of the PRNG from an input stream.

• std::ostream & save (std::ostream &os) const

Saves the state of the PRNG to an output stream.

Private Member Functions

• RandomDevices ()

Initializes and seeds the random number generators.

• \sim RandomDevices ()=default

Default destructor.

Private Attributes

• std::random_device rd_

used to seed std::mt19937 prng_

std::mt19937 prng_

Mersenne twister random number generator.

Friends

class internal::Singleton < RandomDevices >

Additional Inherited Members

7.53.1 Detailed Description

Singleton class that manages the source of randomness in the library.

Consists of a wrapper around an std::mt19937 Mersenne twister random number generator engine and an std ∴ ::random_device engine. The latter is used to seed the Mersenne twister.

Warning

This class DOES NOT seed the standard C number generator used by Eigen::Matrix::Random(), since it is not thread safe. Do not use Eigen::Matrix::Random() or functions that depend on the C style random number engine, but use qpp::rand() instead!

7.53.2 Constructor & Destructor Documentation

7.53.2.1 RandomDevices()

```
qpp::RandomDevices::RandomDevices ( ) [inline], [private]
```

Initializes and seeds the random number generators.

7.53.2.2 ∼RandomDevices()

```
qpp::RandomDevices::~RandomDevices ( ) [private], [default]
```

Default destructor.

7.53.3 Member Function Documentation

```
7.53.3.1 get_prng()
```

```
std::mt19937& qpp::RandomDevices::get_prng ( ) [inline]
```

Returns a reference to the internal PRNG object.

Returns

Reference to the internal PRNG object

7.53.3.2 load()

Loads the state of the PRNG from an input stream.

Do					
Pа	ra	m	eı	re.	rs

```
is Input stream
```

Returns

The input stream

```
7.53.3.3 save()
```

Saves the state of the PRNG to an output stream.

Parameters

```
os Output stream
```

Returns

The output stream

7.53.4 Friends And Related Function Documentation

```
7.53.4.1 internal::Singleton < RandomDevices >
```

```
\label{lem:class} \mbox{friend class internal::Singleton} < \mbox{RandomDevices} > \mbox{ [friend]}
```

7.53.5 Member Data Documentation

```
7.53.5.1 prng_
```

```
std::mt19937 qpp::RandomDevices::prng_ [private]
```

Mersenne twister random number generator.

```
7.53.5.2 rd_
```

```
std::random_device qpp::RandomDevices::rd_ [private]
```

used to seed std::mt19937 prng

The documentation for this class was generated from the following file:

· classes/random_devices.h

7.54 qpp::internal::Singleton < T > Class Template Reference

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

```
#include <internal/classes/singleton.h>
```

Static Public Member Functions

- static T & get_instance () noexcept(std::is_nothrow_constructible < T >::value)
- static T & get_thread_local_instance () noexcept(std::is_nothrow_constructible < T >::value)

Protected Member Functions

- Singleton () noexcept=default
- Singleton (const Singleton &)=delete
- Singleton & operator= (const Singleton &)=delete
- virtual ∼Singleton ()=default

7.54.1 Detailed Description

```
template<typename T>
class qpp::internal::Singleton< T>
```

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

To implement a singleton, derive your class from qpp::internal::Singleton, make qpp::internal::Singleton a friend of your class, then declare the constructor and destructor of your class as private. To get an instance, use the static member function qpp::internal::Singleton::get_instance() (qpp::internal::Singleton::get_thread_local_cinstance()), which returns a reference (thread_local_reference) to your newly created singleton (thread-safe in C++11).

Example:

See also

Code of qpp::Codes, qpp::Gates, qpp::Init, qpp::RandomDevices, qpp::States or qpp.h for real world examples of usage.

7.54.2 Constructor & Destructor Documentation

7.54.3 Member Function Documentation

7.54.3.1 get_instance()

```
template<typename T>
static T& qpp::internal::Singleton< T >::get_instance ( ) [inline], [static], [noexcept]
```

7.54.3.2 get_thread_local_instance()

```
template<typename T>
static T& qpp::internal::Singleton< T >::get_thread_local_instance ( ) [inline], [static],
[noexcept]
```

7.54.3.3 operator=()

The documentation for this class was generated from the following file:


• internal/classes/singleton.h

7.55 qpp::exception::SizeMismatch Class Reference


Size mismatch exception.

```
#include <classes/exception.h>
```

Inheritance diagram for qpp::exception::SizeMismatch:



Collaboration diagram for qpp::exception::SizeMismatch:



Public Member Functions

std::string type_description () const override
 Exception type description.

7.55.1 Detailed Description

Size mismatch exception.

Sizes do not match

7.55.2 Member Function Documentation

7.55.2.1 type_description()

std::string qpp::exception::SizeMismatch::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.56 qpp::States Class Reference


const Singleton class that implements most commonly used states

#include <classes/states.h>

Inheritance diagram for qpp::States:



Collaboration diagram for qpp::States:



Public Member Functions

• ket mes (idx d=2) const

Maximally entangled state of 2 qudits.

• ket zero (idx n, idx d=2) const

Zero state of n qudits.

• ket one (idx n, idx d=2) const

One state of n qudits.

• ket jn (idx j, idx n, idx d=2) const

 $|j\rangle^{\otimes n}$ state of n qudits

· ket plus (idx n) const

Plus state of n qubits.

• ket minus (idx n) const

Minus state of n qubits.

Public Attributes

```
    ket x0 {ket::Zero(2)}
```

Pauli Sigma-X 0-eigenstate |+>

ket x1 {ket::Zero(2)}

Pauli Sigma-X 1-eigenstate |->

ket y0 {ket::Zero(2)}

Pauli Sigma-Y 0-eigenstate | y+>

ket y1 {ket::Zero(2)}

Pauli Sigma-Y 1-eigenstate | y->

ket z0 {ket::Zero(2)}

Pauli Sigma-Z 0-eigenstate | 0>

ket z1 {ket::Zero(2)}

Pauli Sigma-Z 1-eigenstate | 1>

cmat px0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.

cmat px1 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.

cmat py0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-Y 0-eigenstate |y+>< y+|.

cmat py1 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.

cmat pz0 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.

• cmat pz1 {cmat::Zero(2, 2)}

Projector onto the Pauli Sigma-Z 1-eigenstate | 1><1|.

ket b00 {ket::Zero(4)}

Bell-00 state (following the convention in Nielsen and Chuang)

ket b01 {ket::Zero(4)}

Bell-01 state (following the convention in Nielsen and Chuang)

ket b10 {ket::Zero(4)}

Bell-10 state (following the convention in Nielsen and Chuang)

ket b11 {ket::Zero(4)}

Bell-11 state (following the convention in Nielsen and Chuang)

cmat pb00 {cmat::Zero(4, 4)}

Projector onto the Bell-00 state.

cmat pb01 {cmat::Zero(4, 4)}

Projector onto the Bell-01 state.

cmat pb10 {cmat::Zero(4, 4)}

Projector onto the Bell-10 state.

cmat pb11 {cmat::Zero(4, 4)}

Projector onto the Bell-11 state.

ket GHZ {ket::Zero(8)}

GHZ state.

ket W {ket::Zero(8)}

W state.

cmat pGHZ {cmat::Zero(8, 8)}

Projector onto the GHZ state.

cmat pW {cmat::Zero(8, 8)}

Projector onto the W state.

Private Member Functions

- States ()
- ∼States ()=default

Default destructor.

Friends

class internal::Singleton < const States >

Additional Inherited Members

7.56.1 Detailed Description

const Singleton class that implements most commonly used states

7.56.2 Constructor & Destructor Documentation

```
7.56.2.1 States()

qpp::States::States ( ) [inline], [private]

Initialize the states

7.56.2.2 ~States()

qpp::States::~States ( ) [private], [default]
```

Default destructor.

7.56.3 Member Function Documentation

7.56.3.1 jn()

 $|j\rangle^{\otimes n}$ state of *n* qudits

Parameters

j	Non-negative integer
n	Non-negative integer
d	Subsystem dimensions

Returns

 $|j\rangle^{\otimes n}$ state of n qudits

7.56.3.2 mes()

```
ket qpp::States::mes (
idx d = 2 ) const [inline]
```

Maximally entangled state of 2 qudits.

Parameters

```
d Subsystem dimensions
```

Returns

Maximally entangled state $\frac{1}{\sqrt{d}} \sum_{j=0}^{d-1} |jj\rangle$ of 2 qudits

7.56.3.3 minus()

```
ket qpp::States::minus (
        idx n ) const [inline]
```

Minus state of n qubits.

Parameters

n Non-negative integer

Returns

Minus state $|-\rangle^{\otimes n}$ of n qubits

7.56.3.4 one()

```
ket qpp::States::one (
          idx n,
          idx d = 2) const [inline]
```

One state of *n* qudits.

Parameters

n	Non-negative integer
d	Subsystem dimensions

Returns

One state $|1\rangle^{\otimes n}$ of n qudits

7.56.3.5 plus()

```
ket qpp::States::plus (
        idx n ) const [inline]
```

Plus state of *n* qubits.

Parameters

n Non-negative integer

Returns

Plus state $|+\rangle^{\otimes n}$ of n qubits

7.56.3.6 zero()

```
ket qpp::States::zero (
        idx n,
        idx d = 2 ) const [inline]
```

Zero state of *n* qudits.

Parameters

n	Non-negative integer
d	Subsystem dimensions

Returns

Zero state $|0\rangle^{\otimes n}$ of n qudits

7.56.4 Friends And Related Function Documentation

```
7.56.4.1 internal::Singleton < const States >
```

```
friend class internal::Singleton< const States > [friend]
```

7.56.5 Member Data Documentation

```
7.56.5.1 b00
```

```
ket qpp::States::b00 {ket::Zero(4)}
```

Bell-00 state (following the convention in Nielsen and Chuang)

7.56.5.2 b01

```
ket qpp::States::b01 {ket::Zero(4)}
```

Bell-01 state (following the convention in Nielsen and Chuang)

```
7.56.5.3 b10
ket qpp::States::b10 {ket::Zero(4)}
Bell-10 state (following the convention in Nielsen and Chuang)
7.56.5.4 b11
ket qpp::States::b11 {ket::Zero(4)}
Bell-11 state (following the convention in Nielsen and Chuang)
7.56.5.5 GHZ
ket qpp::States::GHZ {ket::Zero(8)}
GHZ state.
7.56.5.6 pb00
cmat qpp::States::pb00 {cmat::Zero(4, 4)}
Projector onto the Bell-00 state.
7.56.5.7 pb01
cmat qpp::States::pb01 {cmat::Zero(4, 4)}
Projector onto the Bell-01 state.
```

7.56.5.8 pb10

```
cmat qpp::States::pb10 {cmat::Zero(4, 4)}
```

Projector onto the Bell-10 state.

```
7.56.5.9 pb11
cmat qpp::States::pb11 {cmat::Zero(4, 4)}
Projector onto the Bell-11 state.
7.56.5.10 pGHZ
cmat qpp::States::pGHZ {cmat::Zero(8, 8)}
Projector onto the GHZ state.
7.56.5.11 pW
cmat qpp::States::pW {cmat::Zero(8, 8)}
Projector onto the W state.
7.56.5.12 px0
cmat qpp::States::px0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-X 0-eigenstate |+><+|.
7.56.5.13 px1
cmat qpp::States::px1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-X 1-eigenstate |-><-|.
7.56.5.14 py0
cmat qpp::States::py0 {cmat::Zero(2, 2)}
```

Projector onto the Pauli Sigma-Y 0-eigenstate |y+><y+|.

```
7.56.5.15 py1
cmat qpp::States::py1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Y 1-eigenstate |y-><y-|.
7.56.5.16 pz0
cmat qpp::States::pz0 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 0-eigenstate |0><0|.
7.56.5.17 pz1
cmat qpp::States::pz1 {cmat::Zero(2, 2)}
Projector onto the Pauli Sigma-Z 1-eigenstate |1><1|.
7.56.5.18 W
ket qpp::States::W {ket::Zero(8)}
W state.
7.56.5.19 x0
ket qpp::States::x0 {ket::Zero(2)}
Pauli Sigma-X 0-eigenstate |+>
7.56.5.20 x1
ket qpp::States::x1 {ket::Zero(2)}
Pauli Sigma-X 1-eigenstate |->
```

```
7.56.5.21 y0
ket qpp::States::y0 {ket::Zero(2)}
Pauli Sigma-Y 0-eigenstate |y+>
7.56.5.22 y1
ket qpp::States::y1 {ket::Zero(2)}
Pauli Sigma-Y 1-eigenstate |y->
7.56.5.23 z0
ket qpp::States::z0 {ket::Zero(2)}
Pauli Sigma-Z 0-eigenstate |0>
7.56.5.24 z1
ket qpp::States::z1 {ket::Zero(2)}
Pauli Sigma-Z 1-eigenstate |1>
The documentation for this class was generated from the following file:
```


· classes/states.h

7.57 qpp::exception::SubsysMismatchDims Class Reference


Subsystems mismatch dimensions exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::SubsysMismatchDims:



Collaboration diagram for qpp::exception::SubsysMismatchDims:



Public Member Functions

std::string type_description () const override
 Exception type description.

7.57.1 Detailed Description

Subsystems mismatch dimensions exception.

std::vector<idx> of subsystem labels has duplicates, or has entries that are larger than the size of the std \leftrightarrow ::vector<idx> of dimensions

7.57.2 Member Function Documentation

7.57.2.1 type_description()

std::string qpp::exception::SubsysMismatchDims::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.58 qpp::Timer < T, CLOCK_T > Class Template Reference


Chronometer.

```
#include <classes/timer.h>
```

Inheritance diagram for qpp::Timer < T, CLOCK T >:



Collaboration diagram for qpp::Timer< T, CLOCK_T >:



Public Member Functions

• Timer () noexcept

Constructs an instance with the current time as the starting point.

· void tic () noexcept

Resets the chronometer.

• const Timer & toc () noexcept

Stops the chronometer.

• double tics () const noexcept

Time passed in the duration specified by T.

• template<typename U = T>

U get_duration () const noexcept

Duration specified by U.

• Timer (const Timer &)=default

Default copy constructor.

• Timer (Timer &&)=default

Default move constructor.

• Timer & operator= (const Timer &)=default

Default copy assignment operator.

• Timer & operator= (Timer &&)=default

Default move assignment operator.

• virtual \sim Timer ()=default

Default virtual destructor.

Protected Attributes

- CLOCK_T::time_point start_
- CLOCK_T::time_point end_

Private Member Functions

• std::ostream & display (std::ostream &os) const override

qpp::IDisplay::display() override

7.58.1 Detailed Description

 $template < typename\ T = std::chrono::duration < double >, typename\ CLOCK_T = std::chrono::steady_clock > class\ qpp::Timer < T,\ CLOCK_T >$

Chronometer.

Template Parameters

Τ	Tics duration, default is std::chrono::duration <double, 1="">, i.e. seconds in double precision</double,>
CLOCK⊷	Clock's type, default is std::chrono::steady_clock, not affected by wall clock changes during runtime
_T	

7.58.2 Constructor & Destructor Documentation

```
7.58.2.1 Timer() [1/3]
```

```
 \begin{tabular}{ll} template < typename T = std::chrono::duration < double>, typename CLOCK_T = std::chrono::steady \leftarrow \_clock> \\ qpp::Timer < T, CLOCK_T >::Timer ( ) [inline], [noexcept] \\ \end{tabular}
```

Constructs an instance with the current time as the starting point.

```
7.58.2.2 Timer() [2/3]
```

Default copy constructor.

```
7.58.2.3 Timer() [3/3]
```

Default move constructor.

7.58.2.4 \sim Timer()

```
\label{template} $$ \ensuremath{\sf template}$ $$ \ensurem
```

Default virtual destructor.

7.58.3 Member Function Documentation

7.58.3.1 display()

qpp::IDisplay::display() override

Writes to the output stream the number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc().

Parameters

os Output stream passed by reference

Returns

Reference to the output stream

Implements qpp::IDisplay.

7.58.3.2 get_duration()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
template<typename U = T>
U qpp::Timer< T, CLOCK_T >::get_duration ( ) const [inline], [noexcept]
```

Duration specified by U.

Template Parameters

U | Duration, default is T, which defaults to std::chrono::duration<double, 1>, i.e. seconds in double precision

Returns

Duration that passed between the instantiation/reset and invocation of qpp::Timer::toc()

```
7.58.3.3 operator=() [1/2]
```

Default copy assignment operator.

```
7.58.3.4 operator=() [2/2]
```

Default move assignment operator.

7.58.3.5 tic()

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady←
_clock>
void qpp::Timer< T, CLOCK_T >::tic ( ) [inline], [noexcept]
```

Resets the chronometer.

Resets the starting/ending point to the current time

7.58.3.6 tics()

```
 \begin{tabular}{ll} template < typename T = std::chrono::duration < double >, typename CLOCK_T = std::chrono::steady \leftarrow \_clock > \\ double qpp::Timer < T, CLOCK_T >::tics ( ) const [inline], [noexcept] \\ \end{tabular}
```

Time passed in the duration specified by T.

Returns

Number of tics (specified by T) that passed between the instantiation/reset and invocation of qpp::Timer::toc()

7.58.3.7 toc()

```
\label{lock-type-ame} $$ $$ template<typename T = std::chrono::steady \leftarrow \_clock> $$ const Timer& qpp::Timer< T, CLOCK_T >::toc ( ) [inline], [noexcept] $$
```

Stops the chronometer.

Set the current time as the ending point

Returns

Reference to the current instance

7.58.4 Member Data Documentation

7.58.4.1 end_

```
 \begin{tabular}{ll} template < type name T = std::chrono::duration < double>, type name CLOCK_T = std::chrono::steady \leftarrow \_clock> \\ CLOCK_T::time\_point qpp::Timer < T, CLOCK_T > ::end_ [protected] \\ \end{tabular}
```

7.58.4.2 start_

```
template<typename T = std::chrono::duration<double>, typename CLOCK_T = std::chrono::steady
_clock>
CLOCK_T::time_point qpp::Timer< T, CLOCK_T >::start_ [protected]
```

The documentation for this class was generated from the following file:


· classes/timer.h

7.59 qpp::exception::TypeMismatch Class Reference


Type mismatch exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::TypeMismatch:



Collaboration diagram for qpp::exception::TypeMismatch:



Public Member Functions

• std::string type_description () const override Exception type description.

7.59.1 Detailed Description

Type mismatch exception.

Scalar types do not match

7.59.2 Member Function Documentation

7.59.2.1 type_description()

std::string qpp::exception::TypeMismatch::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


• classes/exception.h

7.60 qpp::exception::UndefinedType Class Reference


Not defined for this type exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::UndefinedType:



Collaboration diagram for qpp::exception::UndefinedType:



Public Member Functions

• std::string type_description () const override Exception type description.

7.60.1 Detailed Description

Not defined for this type exception.

Templated specialization is not defined for this type

7.60.2 Member Function Documentation

7.60.2.1 type_description()

std::string qpp::exception::UndefinedType::type_description () const [inline], [override],
[virtual]

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.61 qpp::exception::Unknown Class Reference


Unknown exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::Unknown:



Collaboration diagram for qpp::exception::Unknown:



Public Member Functions

• std::string type_description () const override Exception type description.

7.61.1 Detailed Description

Unknown exception.

Thrown when no other exception is suitable (not recommended, it is better to define another suitable exception type)

7.61.2 Member Function Documentation

7.61.2.1 type_description()

std::string qpp::exception::Unknown::type_description () const [inline], [override], [virtual]
Exception type description.

Returns

Exception type description


Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:


· classes/exception.h

7.62 qpp::QCircuitDescription::iterator::value_type_ Struct Reference

Inheritance diagram for qpp::QCircuitDescription::iterator::value_type_:



Collaboration diagram for qpp::QCircuitDescription::iterator::value_type_:



Public Member Functions

- value_type_ (const value_type_ &)=default
 Default copy constructor.
- value_type_ & operator= (const value_type_ &)=default
 Default copy assignment operator.
- value_type_ (const QCircuitDescription *value_type_qcd)
- std::ostream & display (std::ostream &os) const override

qpp::IDisplay::display() override

Public Attributes

- bool is_measurement_ {false}
 current step is a measurement
- idx m_ip_ {idx_infty}

measurements instruction pointer

- idx q_ip_ {idx_infty} gates instruction pointer
- idx ip_ {idx_infty}
- const QCircuitDescription * value_type_qcd_

7.62.1 Constructor & Destructor Documentation

7.62.2 Member Function Documentation

```
7.62.2.1 display()
```

qpp::IDisplay::display() override

Writes to the output stream the textual representation of the iterator de-referenced element

Parameters

```
os Output stream passed by reference
```

Returns

Reference to the output stream

Implements qpp::IDisplay.

```
7.62.2.2 operator=()
```

Default copy assignment operator.

Returns

Reference to the current instancenon-owning pointer to the parent iterator

7.62.3 Member Data Documentation

```
7.62.3.1 ip_
idx qpp::QCircuitDescription::iterator::value_type_::ip_ {idx_infty}
pointer
total (measurements + gates) instruction
7.62.3.2 is_measurement_
\verb|bool| qpp::QCircuitDescription::iterator::value\_type\_::is\_measurement\_ \{false\}|
current step is a measurement
7.62.3.3 m_ip_
idx qpp::QCircuitDescription::iterator::value_type_::m_ip_ {idx_infty}
measurements instruction pointer
7.62.3.4 q_ip_
idx qpp::QCircuitDescription::iterator::value_type_::q_ip_ {idx_infty}
gates instruction pointer
7.62.3.5 value_type_qcd_
const QCircuitDescription* qpp::QCircuitDescription::iterator::value_type_::value_type_qcd_
The documentation for this struct was generated from the following file:
```

Generated by Doxygen


· classes/circuits.h

7.63 qpp::exception::ZeroSize Class Reference


Object has zero size exception.

#include <classes/exception.h>

Inheritance diagram for qpp::exception::ZeroSize:



Collaboration diagram for qpp::exception::ZeroSize:



Public Member Functions

std::string type_description () const override
 Exception type description.

7.63.1 Detailed Description

Object has zero size exception.

Zero sized object, e.g. empty Eigen::Matrix or std::vector with no elements

7.63.2 Member Function Documentation

7.63.2.1 type_description()

```
std::string qpp::exception::ZeroSize::type_description ( ) const [inline], [override], [virtual]
```

Exception type description.

Returns

Exception type description

Implements qpp::exception::Exception.

The documentation for this class was generated from the following file:

· classes/exception.h


Chapter 8

File Documentation

8.1 classes/circuits.h File Reference

Support for qudit quantum circuits.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::QCircuitDescription

Quantum circuit description class.

• class qpp::QCircuitDescription::iterator

Quantum circuit description bound-checking (safe) iterator.

- struct qpp::QCircuitDescription::iterator::value_type_
- struct qpp::QCircuitDescription::GateStep

One step consisting only of gates/operators in the circuit.

• struct qpp::QCircuitDescription::MeasureStep

One step consisting only of measurements in the circuit.

· class qpp::QCircuit

Quantum circuit simulator class.

324 File Documentation

Namespaces

• qpp

Quantum++ main namespace.


8.1.1 Detailed Description

Support for qudit quantum circuits.

8.2 classes/codes.h File Reference

Quantum error correcting codes.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::Codes

const Singleton class that defines quantum error correcting codes

Namespaces

• qpp

Quantum++ main namespace.


8.2.1 Detailed Description

Quantum error correcting codes.

8.3 classes/exception.h File Reference

Exceptions.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::exception::Exception

Base class for generating Quantum++ custom exceptions.

· class qpp::exception::Unknown

Unknown exception.

class qpp::exception::ZeroSize

Object has zero size exception.

• class qpp::exception::MatrixNotSquare

Matrix is not square exception.

class qpp::exception::MatrixNotCvector

Matrix is not a column vector exception.

· class qpp::exception::MatrixNotRvector

Matrix is not a row vector exception.

• class qpp::exception::MatrixNotVector

Matrix is not a vector exception.

class qpp::exception::MatrixNotSquareNorCvector

Matrix is not square nor column vector exception.

class qpp::exception::MatrixNotSquareNorRvector

Matrix is not square nor row vector exception.

· class qpp::exception::MatrixNotSquareNorVector

Matrix is not square nor vector exception.

class qpp::exception::MatrixMismatchSubsys

Matrix mismatch subsystems exception.

· class qpp::exception::DimsInvalid

Invalid dimension(s) exception.

class qpp::exception::DimsNotEqual

Dimensions not equal exception.

class qpp::exception::DimsMismatchMatrix

Dimension(s) mismatch matrix size exception.

class qpp::exception::DimsMismatchCvector

326 File Documentation

Dimension(s) mismatch column vector size exception.

· class qpp::exception::DimsMismatchRvector

Dimension(s) mismatch row vector size exception.

· class qpp::exception::DimsMismatchVector

Dimension(s) mismatch vector size exception.

class qpp::exception::SubsysMismatchDims

Subsystems mismatch dimensions exception.

· class qpp::exception::PermInvalid

Invalid permutation exception.

class qpp::exception::PermMismatchDims

Permutation mismatch dimensions exception.

· class qpp::exception::NotQubitMatrix

Matrix is not 2 x 2 exception.

class qpp::exception::NotQubitCvector

Column vector is not 2 x 1 exception.

class qpp::exception::NotQubitRvector

Row vector is not 1 x 2 exception.

class qpp::exception::NotQubitVector

Vector is not 2 x 1 nor 1 x 2 exception.

class qpp::exception::NotQubitSubsys

Subsystems are not qubits exception.

· class qpp::exception::NotBipartite

Not bi-partite exception.

· class qpp::exception::NoCodeword

Codeword does not exist exception.

· class qpp::exception::OutOfRange

Argument out of range exception.

· class qpp::exception::TypeMismatch

Type mismatch exception.

class qpp::exception::SizeMismatch

Size mismatch exception.

class qpp::exception::UndefinedType

Not defined for this type exception.

· class qpp::exception::QuditAlreadyMeasured

Qudit was already measured exception.

• class qpp::exception::Duplicates

System (e.g. std::vector) has duplicates exception.

· class qpp::exception::CustomException

Custom exception.

· class qpp::exception::NotImplemented

Code not yet implemented.

· class qpp::exception::InvalidIterator

Invalid iterator.

Namespaces

qpp

Quantum++ main namespace.

• qpp::exception

Quantum++ exception hierarchy namespace.


8.3.1 Detailed Description

Exceptions.

8.4 classes/gates.h File Reference

Quantum gates.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::Gates

const Singleton class that implements most commonly used gates

Namespaces

• qpp

Quantum++ main namespace.

8.4.1 Detailed Description


Quantum gates.

328 File Documentation

8.5 classes/idisplay.h File Reference

Display interface via the non-virtual interface (NVI)

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::IDisplay

Abstract class (interface) that mandates the definition of virtual std::ostream& display(std::ostream& os) const.

Namespaces

• qpp

Quantum++ main namespace.


8.5.1 Detailed Description

Display interface via the non-virtual interface (NVI)

8.6 classes/init.h File Reference

Initialization.

This graph shows which files directly or indirectly include this file:



Classes

· class qpp::Init

const Singleton class that performs additional initializations/cleanups

Namespaces

qpp

Quantum++ main namespace.


8.6.1 Detailed Description

Initialization.

8.7 classes/random_devices.h File Reference

Random devices.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::RandomDevices

Singleton class that manages the source of randomness in the library.

Namespaces

• qpp

Quantum++ main namespace.


8.7.1 Detailed Description

Random devices.

8.8 classes/reversible.h File Reference

Support for classical reversible circuits.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::Dynamic_bitset

Dynamic bitset class, allows the specification of the number of bits at runtime (unlike std::bitset<N>)

class qpp::Bit_circuit

Classical reversible circuit simulator.

• struct qpp::Bit_circuit::Gate_count

Namespaces

qpp

Quantum++ main namespace.


8.8.1 Detailed Description

Support for classical reversible circuits.

8.9 classes/states.h File Reference

Quantum states.

This graph shows which files directly or indirectly include this file:



Classes

• class qpp::States

const Singleton class that implements most commonly used states

Namespaces

• qpp

Quantum++ main namespace.


8.9.1 Detailed Description

Quantum states.

8.10 classes/timer.h File Reference

Timing.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::Timer < T, CLOCK_T >
 Chronometer.

Namespaces

• qpp

Quantum++ main namespace.


8.10.1 Detailed Description

Timing.

8.11 constants.h File Reference

Constants.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

• qpp::literals

Functions

- constexpr cplx qpp::literals::operator"" _i (unsigned long long int x) noexcept
 - User-defined literal for complex $i=\sqrt{-1}$ (integer overload)
- constexpr cplx qpp::operator"" _i (long double x) noexcept

User-defined literal for complex $i = \sqrt{-1}$ (real overload)

• cplx qpp::omega (idx D)

D-th root of unity.

Variables

• constexpr double qpp::chop = 1e-10

Used in qpp::disp() for setting to zero numbers that have their absolute value smaller than qpp::chop.

• constexpr double qpp::eps = 1e-12

Used to decide whether a number or expression in double precision is zero or not.

• constexpr idx qpp::maxn = 64

Maximum number of allowed qubits/qudits (subsystems)

• constexpr double qpp::pi = 3.141592653589793238462643383279502884

 π

• constexpr double qpp::ee = 2.718281828459045235360287471352662497

Base of natural logarithm, e.

constexpr double qpp::infty = std::numeric_limits<double>::max()

Used to denote infinity in double precision.

• const idx qpp::idx_infty = static_cast<idx>(-1)

Used to denote the largest unsigned index.


8.11.1 Detailed Description

Constants.

8.12 entanglement.h File Reference

Entanglement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

```
template<typename Derived >
  dyn col vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, const std::vector<
  idx > &dims)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  dyn_col_vect< double > qpp::schmidtcoeffs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt coefficients of the bi-partite pure state A.

    template<typename Derived >

  cmat qpp::schmidtA (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat <a href="mailto:qpp::schmidtA">qpp::schmidtA</a> (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Alice side.

    template<typename Derived >

  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Schmidt basis on Bob side.
template<typename Derived >
  cmat qpp::schmidtB (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt basis on Bob side.
• template<typename Derived >
  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, const std::vector< idx
  > &dims)
      Schmidt probabilities of the bi-partite pure state A.

    template<typename Derived >

  std::vector< double > qpp::schmidtprobs (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Schmidt probabilities of the bi-partite pure state A.
• template<typename Derived >
  double qpp::entanglement (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Entanglement of the bi-partite pure state A.
• template<typename Derived >
  double <a href="mailto:qpp::entanglement">qpp::entanglement</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Entanglement of the bi-partite pure state A.

    template<typename Derived >

  double <a href="mailto:qpp::gconcurrence">qpp::gconcurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      G-concurrence of the bi-partite pure state A.

    template<typename Derived >

  double qpp::negativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double <a href="mailto:qpp::negativity">qpp::negativity</a> (const Eigen::MatrixBase</a> Derived > &A, idx d=2)
      Negativity of the bi-partite mixed state A.
• template<typename Derived >
  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &dims)
      Logarithmic negativity of the bi-partite mixed state A.
template<typename Derived >
  double qpp::lognegativity (const Eigen::MatrixBase< Derived > &A, idx d=2)
      Logarithmic negativity of the bi-partite mixed state A.

    template<typename Derived >

  double <a href="mailto:qpp::concurrence">qpp::concurrence</a> (const Eigen::MatrixBase</a> Derived > &A)
      Wootters concurrence of the bi-partite qubit mixed state A.
```


8.12.1 Detailed Description

Entanglement functions.

8.13 entropies.h File Reference

Entropy functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

```
    template<typename Derived >
        double qpp::entropy (const Eigen::MatrixBase< Derived > &A)
```

von-Neumann entropy of the density matrix A

double qpp::entropy (const std::vector< double > &prob)

Shannon entropy of the probability distribution prob.

 $\bullet \ \ \mathsf{template} \mathord{<} \mathsf{typename} \ \mathsf{Derived} >$

```
double <a href="mailto:qpp::renyi">qpp::renyi</a> (const Eigen::MatrixBase< Derived > &A, double alpha)
```

Renyi- α entropy of the density matrix A, for $\alpha \geq 0$.

double qpp::renyi (const std::vector< double > &prob, double alpha)

Renyi- α entropy of the probability distribution prob, for $\alpha \geq 0.$

• template<typename Derived >

```
double qpp::tsallis (const Eigen::MatrixBase< Derived > &A, double q)
```

Tsallis- q entropy of the density matrix A, for $q \geq 0$.

double qpp::tsallis (const std::vector< double > &prob, double q)

Tsallis- q entropy of the probability distribution prob, for $q \geq 0$.

• template<typename Derived >

double qpp::qmutualinfo (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &subsysA, const std::vector< idx > &subsysB, const std::vector< idx > &dims)

Quantum mutual information between 2 subsystems of a composite system.

• template<typename Derived >

 $\label{lem:double qpp::qmutualinfo} $$ double qpp::qmutualinfo (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &subsysA, const std::vector < idx > &subsysB, idx d=2) $$$

Quantum mutual information between 2 subsystems of a composite system.

8.13.1 Detailed Description

Entropy functions.

8.14 experimental/experimental.h File Reference

Experimental/test functions/classes.

Namespaces

• qpp

Quantum++ main namespace.

· qpp::experimental

Experimental/test functions/classes, do not use or modify.


8.14.1 Detailed Description

Experimental/test functions/classes.

8.15 functions.h File Reference

Generic quantum computing functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

qpp::literals

Functions

```
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::transpose (const Eigen::MatrixBase< Derived > &A)
• template<typename Derived >
  dyn mat< typename Derived::Scalar > qpp::conjugate (const Eigen::MatrixBase< Derived > &A)
      Complex conjugate.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::adjoint (const Eigen::MatrixBase< Derived > &A)
      Adjoint.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::inverse (const Eigen::MatrixBase< Derived > &A)
      Inverse.

    template<typename Derived >

  Derived::Scalar qpp::trace (const Eigen::MatrixBase < Derived > &A)
• template<typename Derived >
  Derived::Scalar <a href="mailto:qpp::det">qpp::det</a> (const Eigen::MatrixBase</a> Derived > &A)

    template<typename Derived >

  Derived::Scalar qpp::logdet (const Eigen::MatrixBase< Derived > &A)
     Logarithm of the determinant.

    template<typename Derived >

  Derived::Scalar <a href="mailto:qpp::sum">qpp::sum</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise sum of A.
template<typename Derived >
  Derived::Scalar <a href="mailto:open:prod">open:prod</a> (const Eigen::MatrixBase</a> Derived > &A)
      Element-wise product of A.

    template<typename Derived >

  double <a href="mailto:qpp::norm">qpp::norm</a> (const Eigen::MatrixBase< Derived > &A)
      Frobenius norm.

    template<typename Derived >

  std::pair< dyn_col_vect< cplx >, cmat > qpp::eig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition.
• template<typename Derived >
  dyn_col_vect< cplx > qpp::evals (const Eigen::MatrixBase< Derived > &A)
      Eigenvalues.
• template<typename Derived >
  cmat qpp::evects (const Eigen::MatrixBase< Derived > &A)
      Eigenvectors.

    template<typename Derived >

  std::pair< dyn_col_vect< double >, cmat > qpp::heig (const Eigen::MatrixBase< Derived > &A)
      Full eigen decomposition of Hermitian expression.

    template<typename Derived >

  dyn_col_vect< double > qpp::hevals (const Eigen::MatrixBase< Derived > &A)
     Hermitian eigenvalues.

    template<typename Derived >

  cmat qpp::hevects (const Eigen::MatrixBase< Derived > &A)
      Eigenvectors of Hermitian matrix.
• template<typename Derived >
  std::tuple< cmat, dyn_col_vect< double >, cmat > qpp::svd (const Eigen::MatrixBase< Derived > &A)
      Full singular value decomposition.
```

```
• template<typename Derived >
  dyn_col_vect< double > qpp::svals (const Eigen::MatrixBase< Derived > &A)
     Singular values.

    template<typename Derived >

  cmat qpp::svdU (const Eigen::MatrixBase< Derived > &A)
     Left singular vectors.
• template<typename Derived >
  cmat <a href="mailto:gpp::svdV">gpp::svdV</a> (const Eigen::MatrixBase</a> Derived > &A)
     Right singular vectors.

    template<typename Derived >

  cmat qpp::funm (const Eigen::MatrixBase< Derived > &A, cplx(*f)(const cplx &))
     Functional calculus f(A)

    template<typename Derived >

  cmat qpp::sqrtm (const Eigen::MatrixBase< Derived > &A)
     Matrix square root.

    template < typename Derived >

  cmat qpp::absm (const Eigen::MatrixBase< Derived > &A)
     Matrix absolute value.
• template<typename Derived >
  cmat qpp::expm (const Eigen::MatrixBase< Derived > &A)
     Matrix exponential.
template<typename Derived >
  cmat qpp::logm (const Eigen::MatrixBase< Derived > &A)
     Matrix logarithm.

    template<typename Derived >

  cmat qpp::sinm (const Eigen::MatrixBase< Derived > &A)
     Matrix sin.
• template<typename Derived >
  cmat gpp::cosm (const Eigen::MatrixBase< Derived > &A)
     Matrix cos.
• template<typename Derived >
  cmat qpp::spectralpowm (const Eigen::MatrixBase< Derived > &A, const cplx z)
     Matrix power.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::powm (const Eigen::MatrixBase< Derived > &A, idx n)
     Fast matrix power based on the SQUARE-AND-MULTIPLY algorithm.
template<typename Derived >
  double <a href="mailto:qpp::schatten">qpp::schatten</a> (const Eigen::MatrixBase</a> Derived > &A, double p)
     Schatten matrix norm.
• template<typename OutputScalar , typename Derived >
  dyn_mat< OutputScalar > qpp::cwise (const Eigen::MatrixBase< Derived > &A, OutputScalar(*f)(const
  typename Derived::Scalar &))
     Functor.
• template<typename T >
  dyn_mat< typename T::Scalar > qpp::kron (const T &head)
     Kronecker product.
• template<typename T , typename... Args>
  dyn mat< typename T::Scalar > qpp::kron (const T &head, const Args &... tail)
     Kronecker product.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::kron (const std::vector< Derived > &As)
     Kronecker product.
```

```
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::kron (const std::initializer_list< Derived > &As)
     Kronecker product.
template<typename Derived >
  dyn mat< typename Derived::Scalar > qpp::kronpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Kronecker power.
template<typename T >
  dyn_mat< typename T::Scalar > qpp::dirsum (const T &head)
     Direct sum.
• template<typename T , typename... Args>
  dyn_mat< typename T::Scalar > qpp::dirsum (const T &head, const Args &... tail)
     Direct sum.

    template < typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::vector< Derived > &As)

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::dirsum (const std::initializer_list< Derived > &As)
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::dirsumpow (const Eigen::MatrixBase< Derived > &A, idx n)
     Direct sum power.
• template<typename Derived >
  dyn mat< typename Derived::Scalar > gpp::reshape (const Eigen::MatrixBase< Derived > &A, idx rows,
  idx cols)
     Reshape.

    template<typename Derived1 , typename Derived2 >

  dyn_mat< typename Derived1::Scalar > qpp::comm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Commutator.
• template<typename Derived1 , typename Derived2 >
  dyn_mat< typename Derived1::Scalar > qpp::anticomm (const Eigen::MatrixBase< Derived1 > &A, const
  Eigen::MatrixBase< Derived2 > &B)
     Anti-commutator.

    template<typename Derived >

  dyn mat< typename Derived::Scalar > qpp::prj (const Eigen::MatrixBase< Derived > &A)
     Projector.
• template<typename Derived >
  dyn_mat< typename Derived::Scalar > qpp::grams (const std::vector< Derived > &As)
     Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::grams (const std::initializer_list< Derived > &As)
     Gram-Schmidt orthogonalization.

    template<typename Derived >

  dyn_mat< typename Derived::Scalar > qpp::grams (const Eigen::MatrixBase< Derived > &A)
     Gram-Schmidt orthogonalization.

    std::vector< idx > qpp::n2multiidx (idx n, const std::vector< idx > &dims)

     Non-negative integer index to multi-index.

    idx qpp::multiidx2n (const std::vector< idx > &midx, const std::vector< idx > &dims)

     Multi-index to non-negative integer index.

    ket qpp::mket (const std::vector< idx > &mask, const std::vector< idx > &dims)

     Multi-partite qudit ket.

    ket qpp::mket (const std::vector < idx > &mask, idx d=2)
```

Multi-partite qudit ket.

cmat qpp::mprj (const std::vector < idx > &mask, const std::vector < idx > &dims)

```
Projector onto multi-partite qudit ket.

    cmat qpp::mprj (const std::vector< idx > &mask, idx d=2)

      Projector onto multi-partite qudit ket.

    template<typename InputIterator >

  std::vector< double > qpp::abssq (InputIterator first, InputIterator last)
      Computes the absolute values squared of an STL-like range of complex numbers.

    template<typename Container >

  std::vector< double > qpp::abssq (const Container &c, typename std::enable_if< is_iterable< Container
  >::value >::type *=nullptr)
      Computes the absolute values squared of an STL-like container.

    template<typename Derived >

  std::vector< double > qpp::abssq (const Eigen::MatrixBase< Derived > &A)
      Computes the absolute values squared of an Eigen expression.

    template<typename InputIterator >

  std::iterator_traits< InputIterator >::value_type qpp::sum (InputIterator first, InputIterator last)
      Element-wise sum of an STL-like range.

    template<typename Container >

  Container::value_type qpp::sum (const Container &c, typename std::enable_if< is_iterable< Container >←
  ::value >::type *=nullptr)
      Element-wise sum of the elements of an STL-like container.
• template<typename InputIterator >
  std::iterator_traits< InputIterator >::value_type qpp::prod (InputIterator first, InputIterator last)
      Element-wise product of an STL-like range.

    template<typename Container >

  Container::value_type qpp::prod (const Container &c, typename std::enable_if< is_iterable< Container >←
  ::value >::type *=nullptr)
      Element-wise product of the elements of an STL-like container.

    template<typename Derived >

  dyn col vect< typename Derived::Scalar > qpp::rho2pure (const Eigen::MatrixBase< Derived > &A)
      Finds the pure state representation of a matrix proportional to a projector onto a pure state.

    template<typename T >

  std::vector< T > qpp::complement (std::vector< T > subsys, idx N)
      Constructs the complement of a subsystem vector.

    template<typename Derived >

  std::vector< double > qpp::rho2bloch (const Eigen::MatrixBase< Derived > &A)
      Computes the 3-dimensional real Bloch vector corresponding to the qubit density matrix A.

    cmat qpp::bloch2rho (const std::vector< double > &r)

      Computes the density matrix corresponding to the 3-dimensional real Bloch vector r.
• template<char... Bits>
  ket qpp::literals::operator" ket ()
      Multi-partite qubit ket user-defined literal.
• template<char... Bits>
  bra qpp::literals::operator"" bra ()
      Multi-partite qubit bra user-defined literal.
template<char... Bits>
  cmat qpp::literals::operator"" _prj ()
     Multi-partite qubit projector user-defined literal.
```


8.15.1 Detailed Description

Generic quantum computing functions.

8.16 input_output.h File Reference

Input/output functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 internal::IOManipEigen qpp::disp (const Eigen::MatrixBase< Derived > &A, double chop=qpp::chop)
 Eigen expression ostream manipulator.

internal::IOManipEigen qpp::disp (cplx z, double chop=qpp::chop)

&separator, const std::string &start="[", const std::string &end="]")

Complex number ostream manipulator.

• template<typename InputIterator > internal::IOManipRange< InputIterator > qpp::disp (InputIterator first, InputIterator last, const std::string

Range ostream manipulator.

• template<typename Container >

internal::IOManipRange< typename Container::const_iterator > qpp::disp (const Container &c, const std⇔ ::string &separator, const std::string &send="]", typename std::enable_if< is_⇔ iterable< Container >::value >::type *=nullptr)

Standard container ostream manipulator. The container must support std::begin(), std::end() and forward iteration.

template<typename PointerType >
 internal::IOManipPointer< PointerType > qpp::disp (const PointerType *p, idx N, const std::string &separator, const std::string &start="[", const std::string &end="]")

C-style pointer ostream manipulator.

 $\bullet \ \ \mathsf{template} \mathord{<} \mathsf{typename} \ \mathsf{Derived} >$

void qpp::save (const Eigen::MatrixBase< Derived > &A, const std::string &fname)

Saves Eigen expression to a binary file (internal format) in double precision.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::load (const std::string &fname)

Loads Eigen matrix from a binary file (internal format) in double precision.


8.16.1 Detailed Description

Input/output functions.

8.17 instruments.h File Reference

Measurement functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, const std::vector< idx > &dims)
 Generalized inner product.

template<typename Derived >

 $\label{lem:dyn_col_vect} $$ dyn_col_vect< typename Derived::Scalar > qpp::ip (const Eigen::MatrixBase< Derived > &phi, const Eigen::MatrixBase< Derived > &psi, const std::vector< idx > &subsys, idx d=2) $$$

Generalized inner product.

ullet template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)

Measures the state vector or density operator A using the set of Kraus operators Ks.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks)

Measures the state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >
 std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase
 Derived > &A, const cmat &U)

Measures the state vector or density matrix A in the orthonormal basis specified by the unitary matrix U.

• template<typename Derived >

std::tuple < idx, std::vector < double >, std::vector < cmat > > qpp::measure (const Eigen::MatrixBase < Derived > &A, const std::vector < cmat > &Ks, const std::vector < idx > &target, const std::vector < idx > &dims)

Measures the part subsys of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template < typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const std::initializer_list< cmat > &Ks, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A using the set of Kraus operators Ks.

• template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, const std::vector< idx > &dims)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

template<typename Derived >

std::tuple< idx, std::vector< double >, std::vector< cmat > > qpp::measure (const Eigen::MatrixBase< Derived > &A, const cmat &V, const std::vector< idx > &target, idx d=2)

Measures the part target of the multi-partite state vector or density matrix A in the orthonormal basis or rank-1 projectors specified by the columns of the matrix V.

• template<typename Derived >

std::tuple < std::vector < idx >, double, cmat > qpp::measure_seq (const Eigen::MatrixBase < Derived > &A, std::vector < idx > target, std::vector < idx > dims)

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.

• template<typename Derived >

 $std::tuple < std::vector < idx >, double, cmat > qpp::measure_seq (const Eigen::MatrixBase < Derived > \&A, std::vector < idx > target, idx d=2)$

Sequentially measures the part target of the multi-partite state vector or density matrix A in the computational basis.


8.17.1 Detailed Description

Measurement functions.

8.18 internal/classes/iomanip.h File Reference

Input/output manipulators.

This graph shows which files directly or indirectly include this file:



Classes

- class qpp::internal::IOManipRange< InputIterator >
- class qpp::internal::IOManipPointer< PointerType >
- class qpp::internal::IOManipEigen

Namespaces

• qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


8.18.1 Detailed Description

Input/output manipulators.

8.19 internal/classes/singleton.h File Reference

Singleton pattern via CRTP.

This graph shows which files directly or indirectly include this file:



Classes

class qpp::internal::Singleton< T >

Singleton policy class, used internally to implement the singleton pattern via CRTP (Curiously recurring template pattern)

Namespaces

• qpp

Quantum++ main namespace.

• qpp::internal

Internal utility functions, do not use them directly or modify them.


8.19.1 Detailed Description

Singleton pattern via CRTP.

8.20 internal/util.h File Reference

Internal utility functions.

This graph shows which files directly or indirectly include this file:



Classes

• struct qpp::internal::Display_Impl_

Namespaces

qpp

Quantum++ main namespace.

· qpp::internal

Internal utility functions, do not use them directly or modify them.

Functions

- void qpp::internal::n2multiidx (idx n, idx numdims, const idx *const dims, idx *result) noexcept
- idx qpp::internal::multiidx2n (const idx *const midx, idx numdims, const idx *const dims) noexcept
- $\bullet \ \ {\it template}{<} {\it typename Derived} >$

bool qpp::internal::check square mat (const Eigen::MatrixBase< Derived > &A)

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

bool qpp::internal::check_vector (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_rvector (const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check cvector (const Eigen::MatrixBase< Derived > &A)

template<typename T >

bool qpp::internal::check nonzero size (const T &x) noexcept

• template<typename T1 , typename T2 >

bool app::internal::check matching sizes (const T1 &lhs, const T2 &rhs) noexcept

- bool qpp::internal::check dims (const std::vector < idx > &dims)
- template<typename Derived >

bool qpp::internal::check_dims_match_mat (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

template<typename Derived >

bool qpp::internal::check_dims_match_cvect (const std::vector < idx > &dims, const Eigen::MatrixBase < Derived > &A)

template<typename Derived >

bool qpp::internal::check_dims_match_rvect (const std::vector< idx > &dims, const Eigen::MatrixBase< Derived > &A)

- bool qpp::internal::check eq dims (const std::vector < idx > &dims, idx dim) noexcept
- bool app::internal::check no duplicates (std::vector< idx > v)
- bool qpp::internal::check_subsys_match_dims (const std::vector< idx > &subsys, const std::vector< idx > &dims)
- $\bullet \ \ {\it template}{<} {\it typename Derived} >$

bool qpp::internal::check_qubit_matrix (const Eigen::MatrixBase< Derived > &A) noexcept

• template<typename Derived >

bool qpp::internal::check_qubit_cvector (const Eigen::MatrixBase< Derived > &A) noexcept

 $\bullet \ \ {\it template}{<} {\it typename Derived} >$

 $bool\ qpp::internal::check_qubit_rvector\ (const\ Eigen::MatrixBase < Derived > \&A)\ noexcept$

• template<typename Derived >

bool qpp::internal::check_qubit_vector (const Eigen::MatrixBase< Derived > &A) noexcept

- bool qpp::internal::check_perm (const std::vector< idx > &perm)
- template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::internal::kron2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::MatrixBase< Derived2 > &B)

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::internal::dirsum2 (const Eigen::MatrixBase< Derived1 > &A, const Eigen::MatrixBase< Derived2 > &B)

• template<typename T >

void qpp::internal::variadic_vector_emplace (std::vector< T > &)

template<typename T , typename First , typename... Args>

void qpp::internal::variadic_vector_emplace (std::vector< T > &v, First &&first, Args &&... args)

- idx qpp::internal::get_num_subsys (idx sz, idx d)
- idx qpp::internal::get_dim_subsys (idx sz, idx N)

8.20.1 Detailed Description

Internal utility functions.

8.21 MATLAB/matlab.h File Reference

Input/output interfacing with MATLAB.

```
#include "mat.h"
#include "mex.h"
```

Namespaces

• qpp

Quantum++ main namespace.

Functions

template<typename Derived >
 std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< cplx > >::type qpp
 ::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a complex Eigen dynamic matrix from a MATLAB .mat file,.

• template<typename Derived >

std::enable_if<!std::is_same< typename Derived::Scalar, cplx >::value, dyn_mat< typename Derived::

Scalar > >::type qpp::loadMATLAB (const std::string &mat_file, const std::string &var_name)

Loads a non-complex Eigen dynamic matrix from a MATLAB .mat file,.

template<typename Derived >
 std::enable_if< std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a complex Eigen dynamic matrix to a MATLAB .mat file,.

• template<typename Derived >

std::enable_if< !std::is_same< typename Derived::Scalar, cplx >::value >::type qpp::saveMATLAB (const Eigen::MatrixBase< Derived > &A, const std::string &mat_file, const std::string &var_name, const std::string &mode)

Saves a non-complex Eigen dynamic matrix to a MATLAB .mat file,.


8.21.1 Detailed Description

Input/output interfacing with MATLAB.

8.22 number_theory.h File Reference

Number theory functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

std::vector< int > qpp::x2contfrac (double x, idx N, idx cut=1e5)

Simple continued fraction expansion.

• double qpp::contfrac2x (const std::vector< int > &cf, idx N=idx(-1))

Real representation of a simple continued fraction.

• bigint qpp::gcd (bigint a, bigint b)

Greatest common divisor of two integers.

bigint qpp::gcd (const std::vector< bigint > &as)

Greatest common divisor of a list of integers.

• bigint qpp::lcm (bigint a, bigint b)

Least common multiple of two integers.

bigint qpp::lcm (const std::vector< bigint > &as)

Least common multiple of a list of integers.

std::vector< idx > qpp::invperm (const std::vector< idx > &perm)

Inverse permutation.

• std::vector< idx > qpp::compperm (const std::vector< idx > &perm, const std::vector< idx > &sigma)

Compose permutations.

std::vector< bigint > qpp::factors (bigint a)

Prime factor decomposition.

• bigint qpp::modmul (bigint a, bigint b, bigint p)

Modular multiplication without overflow.

• bigint qpp::modpow (bigint a, bigint n, bigint p)

Fast integer power modulo p based on the SQUARE-AND-MULTIPLY algorithm.

• std::tuple< bigint, bigint, bigint > qpp::egcd (bigint a, bigint b)

Extended greatest common divisor of two integers.

bigint qpp::modinv (bigint a, bigint p)

Modular inverse of a mod p.

bool qpp::isprime (bigint p, idx k=80)

Primality test based on the Miller-Rabin's algorithm.

• bigint qpp::randprime (bigint a, bigint b, idx N=1000)

Generates a random big prime uniformly distributed in the interval [a, b].

- std::vector< std::pair< int, int > > qpp::convergents (const std::vector< int > &cf)
 Convergents.
- std::vector< std::pair< int, int > > qpp::convergents (double x, idx N)
 Convergents.


8.22.1 Detailed Description

Number theory functions.

8.23 operations.h File Reference

Quantum operation functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 const std::vector< idx > &dims)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

template<typename Derived1 , typename Derived2 >
 dyn_mat< typename Derived1::Scalar > qpp::applyCTRL (const Eigen::MatrixBase< Derived1 > &state,
 const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &ctrl, const std::vector< idx > &target,
 idx d=2)

Applies the controlled-gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived1 , typename Derived2 >

dyn_mat< typename Derived1::Scalar > qpp::apply (const Eigen::MatrixBase< Derived1 > &state, const Eigen::MatrixBase< Derived2 > &A, const std::vector< idx > &target, idx d=2)

Applies the gate A to the part target of the multi-partite state vector or density matrix state.

• template<typename Derived >

```
cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks)
```

Applies the channel specified by the set of Kraus operators Ks to the density matrix A.

template < typename Derived >

cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std \leftrightarrow ::vector< idx > &target, const std::vector< idx > &dims)

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

template<typename Derived >

```
cmat qpp::apply (const Eigen::MatrixBase< Derived > &A, const std::vector< cmat > &Ks, const std 
::vector< idx > &target, idx d=2)
```

Applies the channel specified by the set of Kraus operators Ks to the part target of the multi-partite density matrix A.

cmat qpp::kraus2super (const std::vector< cmat > &Ks)

Superoperator matrix.

cmat qpp::kraus2choi (const std::vector< cmat > &Ks)

Choi matrix.

std::vector< cmat > qpp::choi2kraus (const cmat &A)

Orthogonal Kraus operators from Choi matrix.

cmat qpp::choi2super (const cmat &A)

Converts Choi matrix to superoperator matrix.

cmat qpp::super2choi (const cmat &A)

Converts superoperator matrix to Choi matrix.

 $\bullet \ \ {\it template}{<} {\it typename Derived}>$

Partial trace.

template<typename Derived >

```
dyn_mat< typename Derived::Scalar > qpp::ptrace1 (const Eigen::MatrixBase< Derived > &A, idx d=2)
```

Partial trace.

• template<typename Derived >

```
dyn_mat < typename Derived::Scalar > qpp::ptrace2 (const Eigen::MatrixBase < Derived > &A, const std <math>\leftarrow ::vector < idx > &dims)
```

Partial trace.

• template<typename Derived >

```
dyn_mat< typename Derived::Scalar > qpp::ptrace2 (const Eigen::MatrixBase< Derived > &A, idx d=2)
```

Partial trace.

 $\bullet \ \ \mathsf{template} \mathord{<} \mathsf{typename} \ \mathsf{Derived} >$

Partial trace.

template<typename Derived >

```
dyn_mat< typename Derived::Scalar > qpp::ptrace (const Eigen::MatrixBase< Derived > &A, const std ← ::vector< idx > &target, idx d=2)
```

Partial trace.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, const std::vector< idx > &dims)

Partial transpose.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::ptranspose (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2)

Partial transpose.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &perm, const std::vector< idx > &dims)

Subsystem permutation.

template<typename Derived >

 $dyn_mat < typename Derived::Scalar > qpp::syspermute (const Eigen::MatrixBase < Derived > &A, const std::vector < idx > &perm, idx d=2)$

Subsystem permutation.

template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::applyQFT (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

dyn_mat< typename Derived::Scalar > qpp::applyTFQ (const Eigen::MatrixBase< Derived > &A, const std::vector< idx > &target, idx d=2, bool swap=true)

Applies the inverse (adjoint) qudit quantum Fourier transform to the part target of the multi-partite state vector or density matrix A.

• template<typename Derived >

dyn_col_vect< typename Derived::Scalar > qpp::TFQ (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)

Inverse (adjoint) qudit quantum Fourier transform.

• template<typename Derived >

 $dyn_col_vect< typename Derived::Scalar > qpp::QFT (const Eigen::MatrixBase< Derived > &A, idx d=2, bool swap=true)$

Qudit quantum Fourier transform.

8.23.1 Detailed Description

Quantum operation functions.

8.24 qpp.h File Reference

Quantum++ main header file, includes all other necessary headers.

```
#include <algorithm>
#include <cassert>
#include <chrono>
#include <cmath>
#include <complex>
#include <cstdlib>
#include <cstring>
#include <exception>
#include <fstream>
```

```
#include <functional>
#include <initializer list>
#include <iomanip>
#include <iterator>
#include <limits>
#include <memory>
#include <numeric>
#include <ostream>
#include <random>
#include <sstream>
#include <stdexcept>
#include <string>
#include <tuple>
#include <type_traits>
#include <utility>
#include <vector>
#include <Eigen/Dense>
#include <Eigen/SVD>
#include "types.h"
#include "classes/exception.h"
#include "constants.h"
#include "traits.h"
#include "classes/idisplay.h"
#include "internal/util.h"
#include "internal/classes/iomanip.h"
#include "input_output.h"
#include "internal/classes/singleton.h"
#include "classes/random_devices.h"
#include "random.h"
#include "number_theory.h"
#include "functions.h"
#include "classes/init.h"
#include "classes/codes.h"
#include "classes/gates.h"
#include "classes/states.h"
#include "statistics.h"
#include "operations.h"
#include "entropies.h"
#include "entanglement.h"
#include "classes/timer.h"
#include "instruments.h"
#include "classes/reversible.h"
#include "classes/circuits.h"
```

Namespaces

dbb

Quantum++ main namespace.

Macros

• #define QPP_UNUSED_

8.24.1 Detailed Description

Quantum++ main header file, includes all other necessary headers.

8.24.2 Macro Definition Documentation


8.24.2.1 QPP_UNUSED_

#define QPP_UNUSED_

8.25 random.h File Reference

Randomness-related functions.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Functions

double qpp::rand (double a, double b)

Generates a random real number uniformly distributed in the interval [a, b)

• bigint qpp::rand (bigint a, bigint b)

Generates a random big integer uniformly distributed in the interval [a, b].

idx qpp::randidx (idx a=std::numeric_limits < idx >::min(), idx b=std::numeric_limits < idx >::max())

Generates a random index (idx) uniformly distributed in the interval [a, b].

template<typename Derived >

Derived qpp::rand (idx rows, idx cols, double a=0, double b=1)

Generates a random matrix with entries uniformly distributed in the interval [a, b)

template<>

dmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random real matrix with entries uniformly distributed in the interval [a, b), specialization for double matrices (qpp::dmat)

template<>

cmat qpp::rand (idx rows, idx cols, double a, double b)

Generates a random complex matrix with entries (both real and imaginary) uniformly distributed in the interval [a, b), specialization for complex matrices (qpp::cmat)

template<typename Derived >

Derived qpp::randn (idx rows, idx cols, double mean=0, double sigma=1)

Generates a random matrix with entries normally distributed in N(mean, sigma)

• template<>

dmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random real matrix with entries normally distributed in N(mean, sigma), specialization for double matrices (qpp::dmat)

template<>

cmat qpp::randn (idx rows, idx cols, double mean, double sigma)

Generates a random complex matrix with entries (both real and imaginary) normally distributed in N(mean, sigma), specialization for complex matrices (qpp::cmat)

• double qpp::randn (double mean=0, double sigma=1)

Generates a random real number (double) normally distributed in N(mean, sigma)

cmat qpp::randU (idx D=2)

Generates a random unitary matrix.

cmat qpp::randV (idx Din, idx Dout)

Generates a random isometry matrix.

• std::vector< cmat > qpp::randkraus (idx N, idx D=2)

Generates a set of random Kraus operators.

cmat qpp::randH (idx D=2)

Generates a random Hermitian matrix.

ket qpp::randket (idx D=2)

Generates a random normalized ket (pure state vector)

• cmat qpp::randrho (idx D=2)

Generates a random density matrix.

std::vector< idx > qpp::randperm (idx N)

Generates a random uniformly distributed permutation.

std::vector< double > qpp::randprob (idx N)

Generates a random probability vector uniformly distributed over the probability simplex.


8.25.1 Detailed Description

Randomness-related functions.

8.26 statistics.h File Reference

Statistics functions.

This graph shows which files directly or indirectly include this file:



Namespaces

• qpp

Quantum++ main namespace.

Functions

std::vector< double > qpp::uniform (idx N)

Uniform probability distribution vector.

std::vector< double > qpp::marginalX (const dmat &probXY)

Marginal distribution.

std::vector< double > qpp::marginalY (const dmat &probXY)

Marginal distribution.

• template<typename Container >

double qpp::avg (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_← iterable< Container >::value >::type *=nullptr)

Average.

• template<typename Container >

double qpp::cov (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if< is_iterable< Container >::value >::type *=nullptr)

Covariance.

• template<typename Container >

double qpp::var (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_← iterable< Container >::value >::type *=nullptr)

Variance.

• template<typename Container >

double qpp::sigma (const std::vector< double > &prob, const Container &X, typename std::enable_if< is_ \leftarrow iterable< Container >::value >::type *=nullptr)

Standard deviation.

• template<typename Container >

 $\label{local-container} \begin{tabular}{ll} double & qpp::cor (const dmat &probXY, const Container &X, const Container &Y, typename std::enable_if < is_iterable < Container >::value >::type *=nullptr) \end{tabular}$

Correlation.


8.26.1 Detailed Description

Statistics functions.

8.27 traits.h File Reference

Type traits.

This graph shows which files directly or indirectly include this file:



Classes

struct qpp::make_void< Ts >

Helper for qpp::to_void<> alias template.

struct qpp::is_iterable < T, typename >

Checks whether T is compatible with an STL-like iterable container.

• struct qpp::is_iterable< T, to_void< decltype(std::declval< T >().begin()), decltype(std::declval< T >().comend()), typename T::value_type >>

Checks whether T is compatible with an STL-like iterable container, specialization for STL-like iterable containers.

struct qpp::is_matrix_expression< Derived >

Checks whether the type is an Eigen matrix expression.

struct qpp::is_complex< T >

Checks whether the type is a complex type.

struct qpp::is_complex< std::complex< T >>

Checks whether the type is a complex number type, specialization for complex types.

Namespaces

qpp

Quantum++ main namespace.

Typedefs

```
    template < typename... Ts>
        using qpp::to_void = typename make_void < Ts... > ::type
        Alias template that implements the proposal for void_t.
```


8.27.1 Detailed Description

Type traits.

8.28 types.h File Reference

Type aliases.

This graph shows which files directly or indirectly include this file:



Namespaces

qpp

Quantum++ main namespace.

Typedefs

```
using qpp::idx = std::size_t
```

Non-negative integer index, make sure you use an unsigned type.

- using qpp::bigint = long long int
 - Big integer.
- using qpp::cplx = std::complex < double >

Complex number in double precision.

using qpp::ket = Eigen::VectorXcd

Complex (double precision) dynamic Eigen column vector.

• using qpp::bra = Eigen::RowVectorXcd

Complex (double precision) dynamic Eigen row vector.

using qpp::cmat = Eigen::MatrixXcd

Complex (double precision) dynamic Eigen matrix.

• using qpp::dmat = Eigen::MatrixXd

Real (double precision) dynamic Eigen matrix.

• template<typename Scalar >

Dynamic Eigen matrix over the field specified by Scalar.

• template<typename Scalar >

```
using qpp::dyn_col_vect = Eigen::Matrix< Scalar, Eigen::Dynamic, 1 >
```

Dynamic Eigen column vector over the field specified by Scalar.

 $\bullet \ \ \text{template}{<} \text{typename Scalar} >$

```
using qpp::dyn_row_vect = Eigen::Matrix< Scalar, 1, Eigen::Dynamic >
```

Dynamic Eigen row vector over the field specified by Scalar.

8.28.1	Detailed	Description
--------	----------	--------------------

Type aliases.

8.29 /home/vlad/qpp/README.md File Reference

Index

/home/vlad/qpp/README.md, 358	qpp::States, 300
_to_JSON	b11
qpp::QCircuitDescription, 267	qpp::States, 301
\sim Codes	begin
qpp::Codes, 136	qpp::QCircuitDescription, 267
~Gates	bigint
qpp::Gates, 172	qpp, 26
~IDisplay	Bit_circuit
qpp::IDisplay, 187	gpp::Bit circuit, 131
~Init	bloch2rho
qpp::Init, 190	qpp, 36
~RandomDevices	bra
qpp::RandomDevices, 289	qpp, 26
~Singleton	
qpp::internal::Singleton, 292	c_reg_
\sim States	qpp::QCircuitDescription::MeasureStep, 230
qpp::States, 297	cCTRL_custom
\sim Timer	qpp::QCircuitDescription, 270
qpp::Timer, 308	cCTRL
	qpp::QCircuitDescription, 268, 269
A_	CNOTba
qpp::internal::IOManipEigen, 194	qpp::Gates, 180
absm	CNOT
qpp, 28	qpp::Bit_circuit, 131
abssq	qpp::Bit_circuit::Gate_count, 169
•	qpp::Gates, 180
qpp, 28, 29	•••
adjoint	CTRL_custom
qpp, 30	qpp::QCircuitDescription, 273
all	CTRL
qpp::Dynamic_bitset, 156	qpp::Gates, 173
anticomm	qpp::QCircuitDescription, 271, 272
qpp, 30	cbegin
any	qpp::QCircuitDescription, 268
qpp::Dynamic_bitset, 156	cend
apply	qpp::QCircuitDescription, 270
qpp, 30–32	check cvector
applyCTRL	qpp::internal, 120
qpp, 33, 34	check_dims
applyQFT	qpp::internal, 120
• • •	check_dims_match_cvect
qpp, 34	qpp::internal, 120
applyTFQ	
qpp, 35	check_dims_match_mat
avg	qpp::internal, 121
qpp, 35	check_dims_match_rvect
	qpp::internal, 121
b00	check_eq_dims
qpp::States, 300	qpp::internal, 121
b01	check_matching_sizes
qpp::States, 300	qpp::internal, 121
b10	check no duplicates

qpp::internal, 121	contfrac2x
check_nonzero_size	qpp, 40
qpp::internal, 121	convergents
check_perm	qpp, 41
qpp::internal, 122	cor
check_qubit_cvector	qpp, 42
qpp::internal, 122	cosm
check_qubit_matrix	qpp, 42
qpp::internal, 122	count
check_qubit_rvector	qpp::Dynamic_bitset, 157
qpp::internal, 122	COV
check_qubit_vector	qpp, 42
qpp::internal, 122	cplx
check_rvector	qpp, 26 ctrl_
qpp::internal, 122	qpp::QCircuitDescription::GateStep, 184
check_square_mat	CustomException
qpp::internal, 123	qpp::exception::CustomException, 138
check_subsys_match_dims	cwise
qpp::internal, 123	qpp, 43
check_vector	CZ
qpp::internal, 123 choi2kraus	qpp::Gates, 180
qpp, 36	" 1
choi2super	d_
qpp, 37	qpp::QCircuitDescription, 284
chop	data
qpp, 116	qpp::Dynamic_bitset, 157
chop_	det
qpp::internal::IOManipEigen, 194	qpp, 43
classes/circuits.h, 323	difference_type
classes/codes.h, 324	qpp::QCircuitDescription::iterator, 207
classes/exception.h, 325	dirsum
classes/gates.h, 327	qpp, 44, 45 dirsum2
classes/idisplay.h, 328	qpp::internal, 123
classes/init.h, 328	dirsumpow
classes/random_devices.h, 329	qpp, 46
classes/reversible.h, 330	disp
classes/states.h, 330	qpp, 46–48
classes/timer.h, 331	display
cmat	qpp::Dynamic_bitset, 157
qpp, 26	qpp::IDisplay, 188
Codes	qpp::QCircuit, 255
qpp::Codes, 136	qpp::QCircuitDescription, 273
codeword	qpp::QCircuitDescription::iterator::value_type_←
qpp::Codes, 136	, 318
comm	qpp::Timer, 309
qpp, 37	qpp::internal::IOManipEigen, 194
complement	qpp::internal::IOManipPointer, 196
qpp, 38	qpp::internal::IOManipRange, 199
compperm	display_impl_
qpp, 38	qpp::internal::Display_Impl_, 151
concurrence	dits_
qpp, 38	qpp::QCircuit, 260
conjugate	dmat
qpp, 40	qpp, 26
const_iterator	dyn_col_vect
qpp::QCircuitDescription, 265	qpp, 27
constants.h, 332	dyn_mat

qpp, 27	qpp::QCircuitDescription, 274, 275
dyn_row_vect	gate_
qpp, 27	qpp::QCircuitDescription::GateStep, 184
Dynamic_bitset	gate_count
qpp::Dynamic_bitset, 156	qpp::Bit_circuit, 134
	gate_custom
ee	qpp::QCircuitDescription, 275
qpp, 116	gate fan
egcd	qpp::QCircuitDescription, 276
qpp, 48	gate_type_
eig	qpp::QCircuitDescription::GateStep, 185
qpp, 49	
elem	GateStep
qpp::QCircuitDescription::iterator, 211	qpp::QCircuitDescription::GateStep, 184
end	GateType
qpp::QCircuitDescription, 273, 274	qpp::QCircuitDescription, 265
	Gates
end_	qpp::Gates, 172
qpp::Timer, 311	gates_
qpp::internal::IOManipPointer, 197	qpp::QCircuitDescription, 284
qpp::internal::IOManipRange, 200	gcd
entanglement	qpp, 53, 54
qpp, 49, 50	gconcurrence
entanglement.h, 333	qpp, 54
entropies.h, 335	get
entropy	qpp::Dynamic_bitset, 158
qpp, 50, 51	get_circuit_description
eps	qpp::QCircuit, 255
qpp, 116	
evals	get_d
qpp, 51	qpp::QCircuitDescription, 277
evects	get_dim_subsys
qpp, 52	qpp::internal, 123
Exception	get_dit
qpp::exception::Exception, 167	qpp::QCircuit, 255
expandout	get_dits
qpp::Gates, 173–175	qpp::QCircuit, 256
experimental/experimental.h, 336	get_duration
	qpp::Timer, 309
expm	get_gate_count
qpp, 52	qpp::QCircuitDescription, 277
FRED	get gates
	qpp::QCircuitDescription, 277
qpp::Bit_circuit, 131	get instance
qpp::Bit_circuit::Gate_count, 169	qpp::internal::Singleton, 292
qpp::Gates, 180	get ip
factors	qpp::QCircuit, 256
qpp, 52	get iter
Fd	-
qpp::Gates, 175	qpp::QCircuit, 256
first_	get_m_ip
qpp::internal::IOManipRange, 200	qpp::QCircuit, 256
flip	get_measured
qpp::Dynamic_bitset, 158	qpp::QCircuit, 257
functions.h, 336	qpp::QCircuitDescription, 277, 278
funm	get_measurement_count
qpp, 53	qpp::QCircuitDescription, 278
	get_measurement_steps
GHZ	qpp::QCircuitDescription, 278
qpp::States, 301	get_measurements
gate	qpp::QCircuitDescription, 278

get name	Init
qpp::Gates, 176	qpp::Init, 190
gpp::QCircuitDescription, 279	input_output.h, 341
get nc	instruments.h, 342
qpp::QCircuitDescription, 279	internal/classes/iomanip.h, 343
get non measured	internal/classes/singleton.h, 344
qpp::QCircuitDescription, 279	internal/util.h, 345
get_not_measured	internal::Singleton< const Codes >
gpp::QCircuit, 257	qpp::Codes, 136
get_nq	internal::Singleton< const Gates >
qpp::QCircuitDescription, 279	qpp::Gates, 180
get_num_subsys	internal::Singleton< const Init >
qpp::internal, 123	qpp::Init, 190
get_prng	internal::Singleton< const States >
qpp::RandomDevices, 289	qpp::States, 300
get_probs	internal::Singleton< RandomDevices >
qpp::QCircuit, 257	qpp::RandomDevices, 290
get_psi	inverse
qpp::QCircuit, 258	qpp, 57
get_q_ip	invperm
qpp::QCircuit, 258	qpp, 57
get_relative_pos_	ip
qpp::QCircuit, 258	qpp, 58
get_steps_count	ip_
qpp::QCircuitDescription, 280	<pre>qpp::QCircuitDescription::iterator::value_type_←</pre>
get_thread_local_instance	, 319
qpp::internal::Singleton, 293	is_measurement_
grams	qpp::QCircuitDescription::iterator::value_type_←
qpp, 55	, 319
	is_measurement_step
Н	qpp::QCircuit, 259
qpp::Gates, 181	isprime
heig	qpp, 59
qpp, 56	it_
hevals	qpp::QCircuit, 260
qpp, 56	iterator
hevects	qpp::QCircuitDescription::iterator, 208
qpp, 57	iterator_category
	qpp::QCircuitDescription::iterator, 208
IDisplay	
qpp::IDisplay, 187	jn
IOManipEigen	qpp::States, 298
qpp::internal::IOManipEigen, 193	
IOManipPointer	ket
qpp::internal::IOManipPointer, 196	qpp, 28
IOManipRange	kraus2choi
qpp::internal::IOManipRange, 199	qpp, 59
ld	kraus2super
qpp::Gates, 176	qpp, 60
ld2	kron
qpp::Gates, 181	qpp, 60–62
idx	kron2
qpp, 27	qpp::internal, 124
idx_infty	kronpow
qpp, 116	qpp, 62
index_	last
qpp::Dynamic_bitset, 159	last_
infty	qpp::internal::IOManipRange, 200
qpp, 116	Icm

qpp, 63	mprj
load	qpp, 77
qpp, 63	msg_
qpp::RandomDevices, 289	qpp::exception::Exception, 168
loadMATLAB	multiidx2n
qpp, 64, 65	qpp, 78
logdet	qpp::internal, 124
qpp, 65	0 1001
logm	n2multiidx
qpp, 66	qpp, 78
lognegativity	qpp::internal, 124
qpp, 66, 67	N_
m in	qpp::Dynamic_bitset, 164
m_ip_	qpp::internal::IOManipPointer, 197
<pre>qpp::QCircuitDescription::iterator::value_type_←</pre>	NOT
MATLAB/matlab.h, 347	qpp::Bit_circuit, 132
MODMUL 347	qpp::Bit_circuit::Gate_count, 169
	name_
qpp::Gates, 177 marginalX	qpp::QCircuitDescription, 285
	qpp::QCircuitDescription::GateStep, 185
qpp, 67	qpp::QCircuitDescription::MeasureStep, 230
marginalY	nc_
qpp, 67	qpp::QCircuitDescription, 285
mats_	negativity
qpp::QCircuitDescription::MeasureStep, 230	qpp, 79
maxn	none
qpp, 116	qpp::Dynamic_bitset, 159
measure	norm
qpp, 68–72	qpp, 80
measure_seq qpp, 73, 74	nq_
	qpp::QCircuitDescription, 285
MeasureStep	number_theory.h, 347
qpp::QCircuitDescription::MeasureStep, 229	offset
MeasureType qpp::QCircuitDescription, 266	qpp::Dynamic_bitset, 159
measured_ qpp::QCircuitDescription, 284	omega
	qpp, 80
measurement_steps_ qpp::QCircuitDescription, 284	one qpp::States, 299
measurement_type_	operations.h, 349
qpp::QCircuitDescription::MeasureStep, 230	operator!=
measurements	qpp::Dynamic_bitset, 160
qpp::QCircuitDescription, 285	qpp::QCircuitDescription::iterator, 209
measureV	operator<<
qpp::QCircuitDescription, 280	qpp::IDisplay, 188
measureZ	qpp::QCircuitDescription, 282, 283
qpp::QCircuitDescription, 281	operator*
mes	qpp::QCircuitDescription::iterator, 209
qpp::States, 298	operator++
minus	qpp::QCircuitDescription::iterator, 209
qpp::States, 298	operator-
mket	qpp::Dynamic_bitset, 160
qpp, 74, 75	operator=
modiny	qpp::IDisplay, 188
qpp, 75	qpp::QCircuitDescription::iterator, 210
modmul	qpp::QCircuitDescription::iterator::value_type_←
qpp, 76	, 318
modpow	qpp::Timer, 310
qpp, 76	qpp::internal::IOManipPointer, 196
4PP, 10	apptomaomanipi ontel, 190

qpp::internal::IOManipRange, 199	py0
qpp::internal::Singleton, 293	qpp::States, 302
operator==	py1
qpp::Dynamic_bitset, 160	qpp::States, 302
qpp::QCircuitDescription::iterator, 210	pz0
operator"" _bra	qpp::States, 303
qpp::literals, 125	pz1
operator""_i	gpp::States, 303
qpp, 80	
qpp::literals, 125	q_ip_
operator"" _ket	<pre>qpp::QCircuitDescription::iterator::value_type_←</pre>
qpp::literals, 126	, 319
operator"" _prj	QCircuit
qpp::literals, 126	qpp::QCircuit, 254, 255
app.morate, 120	qpp::QCircuitDescription::iterator, 211
p_	QCircuitDescription
qpp::internal::IOManipPointer, 197	qpp::QCircuitDescription, 266
pGHZ	qpp::QCircuitDescription::iterator, 211
qpp::States, 302	QFT
pb00 00dq	qpp, 88
qpp::States, 301	gpp::QCircuitDescription, 281
pb01	QPP_UNUSED_
qpp::States, 301	qpp.h, 353
pb10	qcd
qpp::States, 301	qpp::QCircuit, 261
pb11	qpp::QCircuitDescription::iterator, 211
qpp::States, 301	qmutualinfo
	•
pi qpp, 117	qpp, 88, 89
	qpp, 13
plus	absm, 28
qpp::States, 299	abssq, 28, 29
pointer 200 months and the second an	adjoint, 30
qpp::QCircuitDescription::iterator, 208	anticomm, 30
powm	apply, 30–32
qpp, 80	applyCTRL, 33, 34
prj	applyQFT, 34
qpp, 81	applyTFQ, 35
prng_	avg, 35
qpp::RandomDevices, 290	bigint, 26
probs_	bloch2rho, 36
qpp::QCircuit, 260	bra, 26
prod	choi2kraus, 36
qpp, 81, 82	choi2super, 37
psi_	chop, 116
qpp::QCircuit, 260	cmat, 26
ptrace	comm, 37
qpp, 83	complement, 38
ptrace1	compperm, 38
qpp, 84	concurrence, 38
ptrace2	conjugate, 40
qpp, 86	contfrac2x, 40
ptranspose	convergents, 41
qpp, 87	cor, 42
pW	cosm, 42
qpp::States, 302	cov, 42
px0	cplx, 26
qpp::States, 302	cwise, 43
px1	det, 43
qpp::States, 302	dirsum, 44, 45
п 1	, ,

dirsumpow, 46	powm, 80
disp, 46–48	prj, 81
dmat, 26	prod, 81, 82
dyn_col_vect, 27	ptrace, 83
dyn_mat, 27	ptrace1, 84
dyn_row_vect, 27	ptrace2, 86
ee, 116	ptranspose, 87
egcd, 48	QFT, 88
eig, 49	qmutualinfo, 88, 89
entanglement, 49, 50	rand, 89–91
entropy, 50, 51	randH, 91
eps, 116	randidx, 93
evals, 51	randket, 93
evects, 52	randkraus, 93
expm, 52	randn, 94, 95
factors, 52	randperm, 96
funm, 53	randprime, 96
gcd, 53, 54	randprob, 97
gconcurrence, 54	randrho, 97
grams, 55	randU, 97
heig, 56	randV, 98
hevals, 56	renyi, 98, 99
hevects, 57	reshape, 99
idx, 27	rho2bloch, 100
idx_infty, 116	rho2pure, 100
infty, 116	save, 101
inverse, 57	saveMATLAB, 101, 102
invperm, 57	schatten, 102
ip, 58	schmidtA, 103
isprime, 59	schmidtB, 103, 104
ket, 28	schmidtcoeffs, 104, 105
kraus2choi, 59	schmidtprobs, 105, 106
kraus2super, 60	sigma, 106
kron, 60–62	sinm, 107
kronpow, 62	spectralpowm, 107
lcm, 63	sqrtm, 108
load, 63	sum, 108, 109
loadMATLAB, 64, 65	super2choi, 109
logdet, 65	svals, 110
logm, 66	svd, 110
lognegativity, 66, 67	svdU, 110
marginalX, 67	svdV, 111
marginalY, 67	syspermute, 111, 112
maxn, 116	TFQ, 112
measure, 68-72	to_void, 28
measure_seq, 73, 74	trace, 112
mket, 74, 75	transpose, 113
modiny, 75	tsallis, 113, 114
modmul, 76	uniform, 114
modpow, 76	var, 115
mprj, 77	x2contfrac, 115
multiidx2n, 78	qpp.h, 351
n2multiidx, 78	QPP UNUSED , 353
negativity, 79	qpp::Bit circuit, 129
norm, 80	Bit circuit, 131
omega, 80	CNOT, 131
operator"" _i, 80	FRED, 131
pi, 117	gate_count, 134
Le.1	gato_000111, 107

NOT, 132	internal::Singleton< const Gates >, 180
reset, 132	MODMUL, 177
SWAP, 132	Rn, 177
TOF, 133	RX, 178
X, 133	RY, 178
qpp::Bit_circuit::Gate_count, 1	
CNOT, 169	S, 181
FRED, 169	SWAPd, 179
NOT, 169	SWAP, 181
SWAP, 169	T, 181
TOF, 169	TOF, 181
X, 169	X, 182
qpp::Codes, 134	Xd, 179
\sim Codes, 136	Y, 182
Codes, 136	Z, 182
codeword, 136	Zd, 179
internal::Singleton< cons	
Type, 135	~IDisplay, 187
qpp::Dynamic_bitset, 153	display, 188
all, 156	lDisplay, 187
any, 156	operator<<, 188
count, 157	operator=, 188
data, 157	qpp::Init, 189
display, 157	∼Init, 190
Dynamic_bitset, 156	Init, 190
flip, 158	internal::Singleton< const Init >, 190
get, 158	qpp::QCircuit, 252
-	
index_, 159	display, 255
N_, 164	dits_, 260
none, 159	get_circuit_description, 255
offset_, 159	get_dit, 255
operator!=, 160	get_dits, 256
operator-, 160	get_ip, <mark>256</mark>
operator==, 160	get_iter, 256
rand, 161	get_m_ip, 256
reset, 161, 162	get measured, 257
set, 162	get_not_measured, 257
size, 163	get_probs, 257
storage size, 163	get_probs, 257
5 — 1	
storage_size_, 164	get_q_ip, 258
storage_type, 156	get_relative_pos_, 258
to_string, 163	is_measurement_step, 259
v_, 164	it_, 260
value_type, 156	probs_, 260
qpp::Gates, 170	psi_, 260
\sim Gates, 172	QCircuit, 254, 255
CNOTba, 180	qcd_, 261
CNOT, 180	reset, 259
CTRL, 173	run, 259
CZ, 180	set_dit, 259
expandout, 173–175	set_measured_, 260
FRED, 180	subsys_, 261
Fd, 175	qpp::QCircuitDescription, 261
Gates, 172	_to_JSON, 267
get_name, 176	begin, 267
H, 181	cCTRL_custom, 270
ld, 176	cCTRL, 268, 269
ld2, 181	CTRL custom, 273
- ,	- · · · · · · · · · · · · · · · ·

	CTRL, 271, 272	iterator, 208
	cbegin, 268	iterator_category, 208
	cend, 270	operator!=, 209
	const_iterator, 265	operator*, 209
	d , 284	operator++, 209
	display, 273	operator=, 210
	end, 273, 274	operator==, 210
	gate, 274, 275	pointer, 208
	gate_custom, 275	QCircuit, 211
	gate_fan, 276	QCircuitDescription, 211
	GateType, 265	qcd_, 211
	gates_, 284	reference, 208
	get_d, 277	set_, 210
	get_gate_count, 277	value_type, 208
	get_gates, 277	qpp::QCircuitDescription::iterator::value_type_, 317
	get_measured, 277, 278	display, 318
	get_measurement_count, 278	ip_, 319
	get_measurement_steps, 278	is_measurement_, 319
	get_measurements, 278	m_ip_, 319
	get_name, 279	operator=, 318
	get_nc, 279	q_ip_, 319
	get_non_measured, 279	value_type_, 318
	get_nq, 279	value_type_qcd_, 319
	get_steps_count, 280	qpp::RandomDevices, 287
	MeasureType, 266	\sim RandomDevices, 289
	measured_, 284	get_prng, 289
	measurement_steps_, 284	internal::Singleton < RandomDevices >, 290
	measurements_, 285	load, 289
	measureV, 280	prng_, 290
	measureZ, 281	RandomDevices, 289
	name_, 285	rd_, 290
	nc_, 285	save, 290
	nq_, 285	qpp::States, 295
	operator<<, 282, 283	\sim States, 297
	QCircuitDescription, 266	b00, 300
	QFT, 281	b01, 300
	steps_cnt_, 285	b10, 300
	TFQ, 282	b11, 301
	to_JSON, 282	GHZ, 301
qpp	::QCircuitDescription::GateStep, 183	internal::Singleton < const States >, 300
	ctrl_, 184	jn, 298
	gate_, 184	mes, 298
	gate_type_, 185	minus, 298
	GateStep, 184	one, 299
	name , 185	pGHZ, 302
	step no , 185	pb00, 301
	target_, 185	pb01, 301
ann	::QCircuitDescription::MeasureStep, 228	pb10, 301
ЧРР	c_reg_, 230	pb11, 301
	mats_, 230	plus, 299
	MeasureStep, 229	pW, 302
	•	px0, 302
	measurement_type_, 230	•
	name_, 230	px1, 302
	step_no_, 230	py0, 302
	target_, 230	py1, 302
~~~	::QCircuitDescription::iterator, 206	pz0, 303
qpp	difference type 007	n=1 202
qpp	difference_type, 207 elem_, 211	pz1, 303 States, 297

W, 303	type_description, 223
x0, 303	qpp::exception::MatrixNotSquareNorVector, 224
x1, 303	type_description, 225
y0, 303	qpp::exception::MatrixNotVector, 226
y1, 304	type description, 227
•	· - · ·
z0, 304	qpp::exception::NoCodeword, 231
z1, 304	type_description, 232
zero, 299	qpp::exception::NotBipartite, 233
qpp::Timer	type_description, 234
$\sim$ Timer, 308	qpp::exception::NotImplemented, 235
display, 309	type_description, 236
end_, 311	qpp::exception::NotQubitCvector, 237
get_duration, 309	type_description, 238
operator=, 310	qpp::exception::NotQubitMatrix, 238
start_, 311	type_description, 240
tic, 310	qpp::exception::NotQubitRvector, 240
tics, 310	type_description, 241
Timer, 308	qpp::exception::NotQubitSubsys, 242
toc, 310	type_description, 243
qpp::Timer< T, CLOCK_T >, 306	qpp::exception::NotQubitVector, 244
qpp::exception, 117	type_description, 245
qpp::exception::CustomException, 137	qpp::exception::OutOfRange, 246
CustomException, 138	type_description, 247
type description, 139	qpp::exception::PermInvalid, 248
• •	
what_, 139	type_description, 249
qpp::exception::DimsInvalid, 140	qpp::exception::PermMismatchDims, 250
type_description, 141	type_description, 251
qpp::exception::DimsMismatchCvector, 141	qpp::exception::QuditAlreadyMeasured, 286
type_description, 143	type_description, 287
qpp::exception::DimsMismatchMatrix, 143	qpp::exception::SizeMismatch, 293
type_description, 144	type_description, 294
qpp::exception::DimsMismatchRvector, 145	qpp::exception::SubsysMismatchDims, 305
type_description, 146	type_description, 306
qpp::exception::DimsMismatchVector, 147	qpp::exception::TypeMismatch, 312
type_description, 148	type_description, 313
qpp::exception::DimsNotEqual, 149	qpp::exception::UndefinedType, 313
type_description, 150	type_description, 315
qpp::exception::Duplicates, 152	qpp::exception::Unknown, 315
type_description, 153	type_description, 316
qpp::exception::Exception, 165	qpp::exception::ZeroSize, 320
Exception, 167	type_description, 321
msg_, 168	qpp::experimental, 119
type_description, 167	qpp::internal, 119
what, 168	check_cvector, 120
	check dims, 120
where_, 168	— · · · · · · · · · · · · · · · · · · ·
qpp::exception::InvalidIterator, 191	check_dims_match_cvect, 120
type_description, 192	check_dims_match_mat, 121
qpp::exception::MatrixMismatchSubsys, 213	check_dims_match_rvect, 121
type_description, 214	check_eq_dims, 121
qpp::exception::MatrixNotCvector, 214	check_matching_sizes, 121
type_description, 216	check_no_duplicates, 121
qpp::exception::MatrixNotRvector, 216	check_nonzero_size, 121
type_description, 217	check_perm, 122
qpp::exception::MatrixNotSquare, 218	check_qubit_cvector, 122
type_description, 219	check_qubit_matrix, 122
qpp::exception::MatrixNotSquareNorCvector, 220	check_qubit_rvector, 122
type_description, 221	check_qubit_vector, 122
qpp::exception::MatrixNotSquareNorRvector, 222	— · —
	- '

check_square_mat, 123	qpp::make_void< Ts >, 212
check_subsys_match_dims, 123	
check_vector, 123	rand
dirsum2, 123	qpp, 89–91
get_dim_subsys, 123	qpp::Dynamic_bitset, 161 randH
get_num_subsys, 123	
kron2, 124	qpp, 91 randidx
multiidx2n, 124	
n2multiidx, 124	qpp, 93 randket
variadic_vector_emplace, 124	
qpp::internal::Display_Impl_, 151	qpp, 93 randkraus
display_impl_, 151	qpp, 93
qpp::internal::IOManipEigen, 192	randn
A_, 194	qpp, 94, 95
chop_, 194	random.h, 353
display, 194	RandomDevices
IOManipEigen, 193	qpp::RandomDevices, 289
qpp::internal::IOManipPointer	randperm
display, 196	qpp, 96
end_, 197	randprime
IOManipPointer, 196	qpp, 96
N_, 197	randprob
operator=, 196	qpp, 97
p_, 197	randrho
separator_, 197	qpp, 97
start_, 197	randU
qpp::internal::IOManipPointer< PointerType >, 195	qpp, 97
qpp::internal::IOManipRange	randV
display, 199	qpp, 98
end_, 200	rd_
first_, 200	qpp::RandomDevices, 290
IOManipRange, 199	reference
last_, 200	qpp::QCircuitDescription::iterator, 208
operator=, 199	renyi
separator_, 200	qpp, 98, 99
start_, 200	reset
qpp::internal::IOManipRange< InputIterator >, 198	qpp::Bit_circuit, 132
qpp::internal::Singleton	qpp::Dynamic_bitset, 161, 162
~Singleton, 292	qpp::QCircuit, 259
get_instance, 292	reshape
get_thread_local_instance, 293	qpp, 99
operator=, 293	rho2bloch
Singleton, 292	qpp, 100
qpp::internal::Singleton< T >, 291	rho2pure
qpp::is_complex< std::complex< T > >, 202	qpp, 100
qpp::is_complex < T >, 201	Rn
qpp::is_iterable < T, to_void < decltype(std::declval < T	qpp::Gates, 177
>().begin()), decltype(std::declval< T >().↔	run
end()), typename T::value_type > >, 204	qpp::QCircuit, 259
qpp::is_iterable < T, typename >, 203	RX
qpp::is_matrix_expression< Derived >, 205	qpp::Gates, 178
qpp::literals, 125	RY
operator"" _bra, 125	qpp::Gates, 178
operator"" _i, 125	RZ
operator"" _ket, 126	qpp::Gates, 178
operator""_prj, 126	C
qpp::make_void	S gpp://Catao. 191
type, 212	qpp::Gates, 181

SWAPd	storage_size_
qpp::Gates, 179	qpp::Dynamic_bitset, 164
SWAP	storage_type
qpp::Bit_circuit, 132	qpp::Dynamic_bitset, 156
qpp::Bit_circuit::Gate_count, 169	subsys_
qpp::Gates, 181	qpp::QCircuit, 261
save	sum
qpp, 101	qpp, 108, 109
qpp::RandomDevices, 290	super2choi
saveMATLAB	qpp, 109
qpp, 101, 102	svals
schatten	qpp, 110
qpp, 102	svd
schmidtA	qpp, 110 svdU
qpp, 103	
schmidtB	qpp, 110 svdV
qpp, 103, 104	
schmidtcoeffs	qpp, 111
qpp, 104, 105	syspermute qpp, 111, 112
schmidtprobs	qpp, 111, 112
qpp, 105, 106	Т
separator_	qpp::Gates, 181
qpp::internal::IOManipPointer, 197	TFQ
qpp::internal::IOManipRange, 200	qpp, 112
set	qpp::QCircuitDescription, 282
qpp::Dynamic_bitset, 162	TOF
set_	qpp::Bit_circuit, 133
qpp::QCircuitDescription::iterator, 210	qpp::Bit_circuit::Gate_count, 169
set_dit	qpp::Gates, 181
qpp::QCircuit, 259	target_
set_measured_	qpp::QCircuitDescription::GateStep, 185
qpp::QCircuit, 260	qpp::QCircuitDescription::MeasureStep, 230
sigma	tic
qpp, 106	qpp::Timer, 310
Singleton	tics
qpp::internal::Singleton, 292	qpp::Timer, 310
sinm	Timer
qpp, 107	qpp::Timer, 308
size	to_JSON
qpp::Dynamic_bitset, 163	qpp::QCircuitDescription, 282
spectralpowm	to_string
qpp, 107	qpp::Dynamic_bitset, 163
sqrtm	to_void
qpp, 108	qpp, 28
start_	toc
qpp::Timer, 311	qpp::Timer, 310
qpp::internal::IOManipPointer, 197	trace
qpp::internal::IOManipRange, 200	qpp, 112
States	traits.h, 356
qpp::States, 297	transpose
statistics.h, 355	qpp, 113
step_no_	tsallis
qpp::QCircuitDescription::GateStep, 185	qpp, 113, 114
qpp::QCircuitDescription::MeasureStep, 230	Type
steps_cnt_	qpp::Codes, 135
qpp::QCircuitDescription, 285	type
storage_size	qpp::make_void, 212
qpp::Dynamic_bitset, 163	type_description

```
qpp::exception::CustomException, 139
                                                        what
    gpp::exception::DimsInvalid, 141
                                                             qpp::exception::Exception, 168
    qpp::exception::DimsMismatchCvector, 143
                                                        what
                                                             qpp::exception::CustomException, 139
    qpp::exception::DimsMismatchMatrix, 144
    qpp::exception::DimsMismatchRvector, 146
                                                        where
    qpp::exception::DimsMismatchVector, 148
                                                             qpp::exception::Exception, 168
    qpp::exception::DimsNotEqual, 150
                                                        Χ
    qpp::exception::Duplicates, 153
                                                             app::Bit circuit, 133
    qpp::exception::Exception, 167
                                                             qpp::Bit circuit::Gate count, 169
    qpp::exception::InvalidIterator, 192
                                                             qpp::Gates, 182
    qpp::exception::MatrixMismatchSubsys, 214
                                                        x0
    qpp::exception::MatrixNotCvector, 216
                                                             qpp::States, 303
    qpp::exception::MatrixNotRvector, 217
                                                        х1
    qpp::exception::MatrixNotSquare, 219
                                                             qpp::States, 303
    qpp::exception::MatrixNotSquareNorCvector, 221
                                                        x2contfrac
    qpp::exception::MatrixNotSquareNorRvector, 223
                                                             qpp, 115
    app::exception::MatrixNotSquareNorVector, 225
                                                        Xd
    qpp::exception::MatrixNotVector, 227
                                                             qpp::Gates, 179
    qpp::exception::NoCodeword, 232
    qpp::exception::NotBipartite, 234
                                                        Υ
    app::exception::NotImplemented, 236
                                                             qpp::Gates, 182
    qpp::exception::NotQubitCvector, 238
                                                        y0
    qpp::exception::NotQubitMatrix, 240
                                                             qpp::States, 303
    qpp::exception::NotQubitRvector, 241
                                                        у1
    qpp::exception::NotQubitSubsys, 243
                                                             qpp::States, 304
    qpp::exception::NotQubitVector, 245
    qpp::exception::OutOfRange, 247
                                                        Ζ
    gpp::exception::PermInvalid, 249
                                                             qpp::Gates, 182
    qpp::exception::PermMismatchDims, 251
                                                        z0
    qpp::exception::QuditAlreadyMeasured, 287
                                                             qpp::States, 304
    qpp::exception::SizeMismatch, 294
                                                        z1
    qpp::exception::SubsysMismatchDims, 306
                                                             qpp::States, 304
    qpp::exception::TypeMismatch, 313
                                                        Zd
    qpp::exception::UndefinedType, 315
                                                             qpp::Gates, 179
    qpp::exception::Unknown, 316
                                                        zero
    qpp::exception::ZeroSize, 321
                                                             qpp::States, 299
types.h, 357
uniform
    qpp, 114
    gpp::Dynamic bitset, 164
value_type
    qpp::Dynamic_bitset, 156
    qpp::QCircuitDescription::iterator, 208
value type
    qpp::QCircuitDescription::iterator::value\_type\_{\leftarrow}
         , 318
value_type_qcd_
    qpp::QCircuitDescription::iterator::value type ←
          , 319
var
    qpp, 115
variadic vector emplace
    qpp::internal, 124
    qpp::States, 303
```

W