
FLASK:

Full-sky Lognormal Astro-fields Simulation Kit Version 2.0



Usage and installation manual

Written by:

Henrique S. Xavier*,†
hsxavier@if.usp.br

Jayesh S. Bhatt* bhatt@physics.org

*University College London, UK †Universidade de São Paulo, Brazil

Contents

1	Disc	laimer		5
2	Wha	at is new	v in Version 2.0	7
3	Inst	allation		9
	3.1	Requir	rements	9
	3.2		ling	9
4	Usas	ze		11
	4.1		FLASK	11
		4.1.1	Quick start	11
		4.1.2	Configuration file formats	11
		4.1.3	Basic operation	12
		4.1.4	Directories and files	13
		4.1.5	Tips and things to keep an eye on	13
		4.1.6	Inner workings	13
		4.1.7	Selection function	15
		4.1.8	Configuration file keywords	16
		4.1.9	Fields information file	29
		4.1.10	Angular power spectra files	31
	4.2		ary codes	32
		4.2.1	Dens2KappaCls	32
		4.2.2	GenStarMask	33
		4.2.3	camb2info.py	33
		4.2.4	class2info.py	33
		4.2.5	ChangeMapResolution.py	33
		4.2.6	prepCambInput.py	33
		4.2.7	prepClassInput.py	34
		4.2.8	summarizeData.py	34
		4.2.9	ViewMap.py	34
		4.2.10		34
		4.2.11	config-changes.sh	35
		4.2.12	joinClFiles.py	35
		4.2.13	MathMap.py	35
		4.2.14	config_to_ini.py	35
Bi	bliogi	aphy		37

Disclaimer

FLASK is free software, written by Henrique S. Xavier; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 2 of the License, or (at your option) any later version.

FLASK is distributed in the hope that it will be useful, but without any warranty; without even the implied warranty of merchantability or fitness for a particular purpose. See the GNU General Public License for more details. You should have received a copy of the GNU General Public License along with FLASK; if not, write to the Free Software Foundation, Inc., 59 Temple Place, Suite 330, Boston, MA 02111-1307 USA.

Thank you for using this software. Please report any bugs to hsxavier@if.usp.br and acknowledge FLASK by citing the publication Xavier et al. (2016).

What is new in Version 2.0

- A Python wrapper has been added, so that FLASK can be invoked as a Python module.
 Optionally, the code can still be compiled the old-fashioned way, through purely a C++ compiler.
- FLASK-generated galaxy catalogues can now have user-defined custom header.
- FLASK-generated FITS files are saved in binary format (which are much smaller and faster to write) and can be overwritten without terminating the code. An option has been added to choose between 32-bit or 64-bit binary format. FITS files can no longer be written in .dat (pure text) format.
- Added longer string support in the input config file.
- Added the option to provide input parameters through a .ini file (in addition to the existing .config format).
- New output directories are created if they do not exist already.
- Option added to select whether shear or reduced sheared should be used while calculating ellipticities.
- Minor bug fixes to improve stability.

Installation

3.1 Requirements

FLASK is a code written in C++ that uses OPENMP for parallelization; HEALPIX¹ for mapping the sky and performing harmonic transforms; the Gnu Scientific Library² (GSL) to generate pseudo-random numbers, to perform Cholesky decompositions and other tasks; and the CFITSIO³ library to input and output FITS files. Apart from HEALPIX, all the remaining dependencies should be available on Linux and Mac repositories. HEALPIX however should be easy to install (just follow their instructions); FLASK requires version 3.11 or later of the C++ HEALPIX implementation due to the T_Healpix_Base<I>::boundaries function, introduced in version 3.11. FLASK has been fully operational under HEALPIX versions 3.11, 3.20 and (since January 2017) 3.31.

In addition, the package comes with a Python wrapper, called PYFLASK, so that it can be invoked from a Python like other Python modules. For this to work, Python must also be installed on your machine.

So far FLASK has been tested only on Linux distributions – Scientific Linux 5.6, Ubuntu 14.04 and Ubuntu 18.04 – and compiled with g++ (GCC) versions 4.4.7, 4.8.1, 4.8.4 and 7.5.0. PYFLASK has been tested with Python 3.6, although it should work just as well with Python 2 with the appropriate modification in the Makefile (see Section 3.2).

In addition to the above, FLASK also includes auxiliary Python and SHELL scripts. These were tested in BASH shell and Python versions 2.7.3 and 2.7.6. The Python scripts require a few packages like NUMPY, SCIPY and HEALPY (which can be installed by following HEALPIX instructions). Check the scripts for further dependencies.

3.2 Compiling

1. Pick the relevant Makefile.

There are two types of Makefiles bundled with FLASK. The file Makefile-cpp-and-python compiles and builds both, a Linux binary through the C++ compiler as well as PYFLASK. The file Makefile-cpp-only skips building the Python wrapper and

http://healpix.jpl.nasa.gov

²http://www.gnu.org/software/gsl

³http://heasarc.gsfc.nasa.gov/fitsio

only builds a simple Linux executable for FLASK. The default is Makefile-cpp-and-python and in the following description we shall assume the user is choosing this Makefile.

2. Modify the Makefile as necessary.

Before compiling, you will have to modify the Makefile in the src sub-directory of FLASK. The following lines must be changed according to the location of the HEALPIX installation directory:

```
HEALDIR = <path to Healpix directory>
CXXHEAL = -I<path to Healpix header files>
LDHEAL = -L<path to Healpix library files>
PYWRAPLIB1 = -I<path to Python development package header files>
```

In case other libraries such as CFITSIO, GSL are installed in non-standard locations, you might need to specify their locations with similar compiler flags (i.e. CXXFITS, LDFITS, CXXGSL and LDGSL, commented in the Makefile). The default compiler in the Makefile is g++, you might need to change the keyword COMP as well if using a different compiler.

3. Build the executable/module.

After modifying the Makefile, copy it as 'Makefile' and run the command make in the src directory. For example:

```
$ cd <Root directory of Flask>/src/
$ cp Makefile-cpp-and-python Makefile
$ make
```

The C++ built executable will be placed in the subdirectory that is defined through the variable BIN in the Makefile. In addition, a Python shared object will be placed in the subdirectory that is defined through the variable PYF in the Makefile, so that PYFLASK can be invoked from within Python as a Python module.

You may add these sub-directories to your PATH environment variable in order to be able to run FLASK, or invoke PYFLASK, anywhere; otherwise, you will require to run it, or import the PYFLASK module, from these subdirectories or to provide the full path as usual.

Usage

4.1 Using FLASK

4.1.1 Quick start

To get a feeling of FLASK and to test if things are working fine, go to the FLASK directory and run the command:

\$./bin/flask example.config

This should result in a clean run (no errors or warnings) and should make FLASK use typical data stored in the data sub-directory to create the most relevant outputs into the example sub-directory (which should be empty), including maps and catalogs simulations. Since writing files to the hard-disk is a slow process, this run will take much longer than an usual FLASK run that only outputs one or two files (text files, in particular, take a long time to write). To figure out what the output files are, check the file example.config and Sec. 4.1.8.

4.1.2 Configuration file formats

Basic control parameters for running FLASK or pyFlask are input through a configuration (ASCII text) file. This file can be in either the .config or the .ini format. A standard example in both these formats is bundled with this software to help the user. In the above example, this file is example.config. This example could as well be run with the .ini format input file:

\$./bin/flask example.ini

Similarly, in the following discussion, examples are given with the .config file format; however, the use of a .ini file in those examples would be equally be valid.

If the configuration file provided by the user is in the .ini format, a corresponding file in the .config format will be created by FLASK in the same directory as where the .ini file resides. The filename extension of this newly created file will, however, be .cfg in order to avoid overwriting any 'real' .config file with a similar name that the user may have placed there. For example, if the standard example is run with the file example .ini as above, a file named example.cfg will be automatically created.

A Python script is included to convert from the .config format to the .ini format (Section 4.2.14).

4.1.3 Basic operation

Here we assume the variables BIN and PYF have the following values in the Makefile:

```
BIN=<Root directory of Flask>/bin
PYF=<Root directory of Flask>/py
```

To run Flask

FLASK is executed through the command line, and it always requires a configuration file (e.g. example.config in the FLASK directory):

```
$ cd <Root directory of Flask>/
$ ./bin/flask <configuration file>
```

Any keyword in the configuration file can be altered from the command line by specifying its name <keyword_i> and value <value_i> after passing the configuration file to FLASK:

```
flask <configuration file> <keyword_1>: <value_1> <keyword_2>: <value_2>...
```

For example,

```
flask example.config RNDSEED: 334 MAP_OUT: ./map-002.dat
```

To run pyFlask through Python

The syntax for running the standard example by invoking the Python module pyFlask from the Linux command prompt would be:

```
$ cd <Root directory of Flask>/
$ python3
>>> from py import pyFlask
>>> pyFlask.flask(["flask","example.config"])
```

The values of keywords in the configuration can be modified on the fly by providing them as successive arguments, separated by commas and surrounded by double quote marks, to the pyFlask module call. For instance, to change the value of the RNDSEED variable to 334, use the following syntax:

```
>>> pyFlask.flask(["flask","example.ini","RNDSEED:","334"])
```

Monitoring or recording the output

FLASK outputs to the screen a comprehensive description of what it is doing. In case you want to store this information for later, you might want to redirect the output to a file, e.g.:

```
flask example.config RNDSEED: 334 MAP_OUT: ./map-002.dat > r334.log
or
flask example.config RNDSEED: 334 MAP_OUT: ./map-002.dat | tee r334.log
```

4.1.4 Directories and files

Any output directories declared in the configuration file that do not already exist will be automatically created by FLASK. If the output directory already exists, FLASK will still run without errors; however, any files already present in those directories will be overwritten if they have the same name as in the configuration file.

Please note: The location of all the directories declared in the configuration file (both, input and output) is with respect to the directory from where FLASK is run. It is <u>not</u> with respect to the directory in which the configuration file resides!

4.1.5 Tips and things to keep an eye on

FLASK's screen output contains a lot of information that may help to reproduce previous runs and output files, understand the simulation process, and identify mistakes and bugs. For instance, it contains the FLASK's version (git commit) and all parameters used. All file outputs are announced with a >> sign and all warnings and errors are announced with!! signs. At the end of the screen output one can see the total number of warnings generated during the run. FLASK was designed to produce warnings for all possible mistakes we could think of, so to correctly use FLASK, make sure that the total number of warnings is always zero or (if it is really necessary) that you understand and can afford specific warnings.

If a regularization of the covariance matrix was requested, check the screen output since it informs you the maximum fractional change applied to them. Also, in Gaussian realisations and in some other situations you may end up with negative galaxy counts, something that is also informed by the screen output. These things can distort your results (and they do not produce warnings), so pay attention to them.

FLASK can output practically all intermediary data it produces. If you get some weird result, you can check the data used in the previous calculation steps to find out where the problem is.

4.1.6 Inner workings

The internal process followed by FLASK is described in Xavier et al. (2016). Fig. 4.1 shows a flow chart that roughly described the operations sequences. Some processes are only performed when simulating lognormal fields (Gaussian simulations may skip




Figure 4.1: FLASK basic flow chart. It starts on the top left corner.

a few of them). Other processes like creating triangular matrices used for generating correlated random variables and performing a density line-of-sight (LoS) integration to get the convergence are optional (they are executed according to the specifications in the configuration file). Here we describe a few processes not discussed in Xavier et al. (2016). The noise creation processes are presented in the description of the keywords for generating outputs (maps, catalogues, etc.) that include these noises (check Sec. 4.1.8).

Computing C_{ℓ} s from $a_{\ell m}$ s

When recovering an angular power spectra C_{ℓ}^{ij} from realized multipoles $a_{\ell m}^i$, the following computation is performed:

$$C_{\ell}^{ij} = \frac{1}{\ell+1} \sum_{m=0}^{\ell} a_{\ell m}^{i} a_{\ell m}^{j*}.$$
 (4.1)

We do not sum over negative ms because the fields are real and therefore $(-1)^m a_{\ell-m}^i = a_{\ell m}^{i*}$.

4.1.7 Selection function

Galaxy fields

When sampling a density field with discrete tracers (e.g. galaxies), the expected number of tracers $\langle N_t(i,j) \rangle$ of type t in each pixel j of the redshift shell i is given by:

$$\langle N_t(i,j)\rangle = \bar{n}_t(i,j)[1+\delta_t(i,j)]\Delta\Omega, \tag{4.2}$$

where $\Delta\Omega$ is the pixel angular area in \arcsin^2 , $\bar{n}_t(i,j)$ is the expected number of tracers t per \arcsin^2 that would be observed in pixel j and redshift shell i in a completely homogeneous universe, $\delta_t(i,j)$ is the tracer t density contrast field generated according to the input power spectra. The actual number of tracers generated in each cell can be sampled from a Poisson distribution with average number given by $\langle N_t(i,j) \rangle$ if the keyword POISSON is set to 1, or from a Gaussian distribution with mean given by $\langle N_t(i,j) \rangle$ and standard deviation $\sigma_G = \sqrt{\bar{n}_t(i,j)\Delta\Omega}$ if POISSON is set to 2 (note that in this case the number of tracers can be non-integer and negative).

The way $\bar{n}_t(i, j)$ behaves depends on the SELEC_TYPE keyword (see Section 4.1.8). If SELEC_TYPE: 0, then $\bar{n}_t(i, j)$ is given by:

$$\bar{n}_t(i,j) = a_s \times S(j) \times W_t(i,j). \tag{4.3}$$

Here, a_s is a scaling factor specified by the SELEC_SCALE keyword, S(j) is an angular mask specified by STARMASK and $W_t(i,j)$ depends on the SELEC_SEPARABLE keyword (see Section 4.1.8). For SELEC_SEPARABLE: 0, $W_t(i,j)$ is given by a set of HEALPIX maps (one for each tracer t and redshift i) with prefixes determined by SELEC_PREFIX. For SELEC_SEPARABLE: 1, we have:

$$W_t(i,j) = A(j) \int_{z_i^{\min}}^{z_i^{\max}} f_t(z) dz, \qquad (4.4)$$

where $f_t(z)$ is a radial selection function for the tracer t given by files with prefix SELEC_Z_PREFIX [the value of $f_t(z)$ is linearly interpolated from the tabulated values]; z_i^{\min} and z_i^{\max} are the minimum and maximum redshifts for the redshift shell i, specified in the file given by the FIELDS_INFO keyword (see also Sec. 4.1.9); and A(j) is an angular selection function given by a single HEALPIX map, passed to SELEC_PREFIX. Note that the units of a_s , S(j), $W_t(i,j)$, $f_t(z)$ and A(j) are arbitrary; however, they must be such that the final units of $\bar{n}_t(i,j)$ are number of tracers per arcmin². In most cases, people choose $f_t(z)$ to carry all the units [i.e. $f_t(z)$ is given as number of galaxies per arcmin², per unit redshift] and leave the remaining terms as dimensionless quantities.

It is also possible to set SELEC_SEPARABLE: 2, a variant of the separable case 1 in which different density tracers have different angular selection functions. In mathematical terms, with this option A(j) in Eq. 4.4 is replaced by $A_t(j)$, and each tracer must have a Healpix map representing $A_t(j)$ with prefix given by SELEC_PREFIX. This allows, for instance, the correlated simulation of multiple surveys.

If SELEC_TYPE: 1, $\bar{n}_t(i,j)$ is given by:

$$\bar{n}_t(i,j) = a_s \times S(j) \times W_t(i,j) \times \rho_t(i), \tag{4.5}$$

where $a_s \times S(j) \times W_t(i,j)$ is the fraction of tracers t that get observed and $\rho_t(i)$ is the true underlying density. This option is currently not implemented. The user can add 2 to both SELEC_TYPE options to set S(j) and S(j) to 1 and use their information only as bookkeeping numbers in the catalogue output (CATALOG_OUT).

Finally, note that the user may describe completely masked out pixels in S(j) and A(j) – and in $W_t(i,j)$ if SELEC_SEPARABLE: 0, i.e. in any HEALPIX map describing the selection function – by zero or by any negative number.

Lensing fields

In most cases, FLASK does not use selection functions assigned to lensing fields (the user does not have to supply and FLASK will not read them) since it is only used to go from galaxy density contrast to galaxy counts. The exception would be if the simulation only includes lensing fields and at least one of the outputs controlled by the following keywords is requested: MAPWER_OUT, MAPWERFITS_PREFIX, ELLIP_MAP_OUT and ELLIPFITS_PREFIX. Since these outputs refer to partial sky, noisy data and the selection function affects them by masking regions and modulating shape noise inside pixels through source density, FLASK assumes that a selection function was provided for the lensing fields and attempts to read it and use it. For ellipticity maps, the selection function is used both to mask out regions where no galaxies were observed and to specify the shape noise at each redshift slice and pixel (check the ELLIP_SIGMA keyword in Sec. 4.1.8 for more details). For the convergence fields, the only effect of the selection function in the current implementation is to mask out specific regions (i.e. no noise is added to the output maps).

If there are galaxy fields in the simulation, FLASK will apply their selection functions to the lensing fields. In this case and in the current implementation, the MAPWER_OUT and MAPWERFITS_PREFIX outputs will produce masked convergence maps only if SELEC_SEPARABLE: 1 (otherwise, FLASK will return unmasked convergence maps). If requested through ELLIP_MAP_OUT or ELLIPFITS_PREFIX, FLASK will create ellipticity maps for each galaxy field provided, using their selection functions to calculate the appropriate shape noise levels.

4.1.8 Configuration file keywords

FLASK is built in a way that all the existing keywords in the code must be present in the configuration file otherwise a warning message is issued; this is to avoid setting keywords to values unknown by the user and to disclose to the user all available options in the code. FLASK will also complain if keywords that do not exist in the code are present in the configuration file or are passed through the command line; keywords are identified by a colon (:) after it, so this should not be used for other purposes inside configuration files. Although the hash (#) is used to identify comments, this is only for aesthetic reasons and does not have any effect on the parsing of the configuration file (# DENS2KAPPA: is still identified as the DENS2KAPPA keyword). More information about this can be found in the example.config file. NOTE: in the current implementation, strings passed to the keywords cannot be longer than 1100 characters. Longer strings may cause a segmentation fault when reading the configuration file.

FLASK goes through a series of sequential computations that transforms the simulated data somehow; after each step, the code can output the current status of the data. These possible outputs are presented in the example.config file in the exact order they are produced. Thus, one can have an idea of the simulation process by reading the output options in that file. All outputs can be turned off by assigning 0 to the respective keyword.

We now provide a description of every keyword available in the code (a brief description of each one is also provided in example.config):

- DIST: This takes as value one string that can be either GAUSSIAN, LOGNORMAL or HOMOGENEOUS, specifying what kind of distribution all the simulated random fields will follow. The HOMOGENEOUS in fact ignores all input power spectra $C(\ell)$ s as if they were all zero and creates homogeneous field maps. Density fields can be later Poisson (or Gaussian) sampled according to the selection function, so the HOMOGENEOUS choice is useful to create the random catalogues used in Landy and Szalay (1993), for instance. Weak lensing shear produced under this choice is currently zero, and ellipticities are completely random according to ELLIP_SIGMA. For simulating Gaussian and lognormal correlated fields simultaneously, one should use the LOGNORMAL choice and adjust the input information so to approximate the desired fields to a Gaussian distribution. Note that the GAUSSIAN option might lead to unphysical field values in some cases (e.g. negative densities), which might cause problems in some simulations steps (like sampling galaxies).
- RNDSEED: This is a single integer number, the seed for the pseudo-random number generator. In fact, the seed is transformed into $N_{\rm proc}$ seeds, where $N_{\rm proc}$ is the number of processors available for parallel computing with OPENMP. This transformation is such that every seed provided to RNDSEED will result in different and exclusive set of $N_{\rm proc}$ "sub-seeds" so that different seeds truly result in independent realisations. Note that a given seed passed to RNDSEED will only result in the same realisation as long as $N_{\rm proc}$ remains the same.
- POISSON: This can be 1, 2 or 0, and specifies if the galaxy density fields should be Poisson sampled, Gaussian sampled or not sampled at all, respectively. If not sampled (useful for debugging reasons), the values attributed to the HEALPIX count maps are the expected number of galaxies (a non-integer number); if Gaussian sampled, these values will be non-integer and they can be negative as well. These maps can then be output through the MAPWER_OUT and MAPWERFITS_PREFIX keywords. Generating a galaxy catalogue from maps with POISSON: 0 or 2 would not make much sense and is likely to cause the code to crash. For more information on the parameters used for the sampling, check Sec. 4.1.7.
- OMEGA_m: This takes a real number that represents the total matter (dark matter plus baryons) density parameter. It is only used if the user sets: (1) DENS2KAPPA: 1; (2) SELEC_TYPE: 1 or SELEC_TYPE: 3; or includes r in the list of catalogue columns CATALOG_COLS and generates a catalogue.
- OMEGA_L: This takes a real number that represents the dark energy density parameter. It is only used if the user sets: (1) DENS2KAPPA: 1; (2) SELEC_TYPE: 1 or

SELEC_TYPE: 3; or includes r in the list of catalogue columns CATALOG_COLS and generates a catalogue.

- W_de: This takes a real number that represents the w_0 parameter of a constant dark energy equation of state. It is only used if the user sets: (1) DENS2KAPPA: 1; (2) SELEC_TYPE: 1 or SELEC_TYPE: 3; or includes r in the list of catalogue columns CATALOG_COLS and generates a catalogue. Currently this is the only kind of dark energy model implemented in the code.
- ELLIP_SIGMA: This takes a real number that represents the standard deviation of the zero mean Gaussian distribution from which each component of a galaxy's intrinsic ellipticity $\varepsilon_s = \varepsilon_{s,1} + i\varepsilon_{s,2}$ is randomly drawn. If ELLIP_SIGMA is set to zero or less, all galaxies are considered circular ($\varepsilon_s = 0$).

The final ellipticity $\varepsilon = \varepsilon_1 + i\varepsilon_2$ of a galaxy in the catalogue (produced by the CATALOG_OUT keyword) is:

$$\varepsilon = \begin{cases} \frac{\varepsilon_{s} + g}{1 + g^{*}\varepsilon_{s}}, & |g| \leq 1; \\ \frac{1 + g\varepsilon_{s}^{*}}{\varepsilon_{s}^{*} + g^{*}}, & |g| > 1; \end{cases}$$

$$(4.6)$$

where $g \equiv \gamma/(1-\kappa)$ is the reduced shear, $\gamma = \gamma_1 + i\gamma_2$ is the shear, κ is the convergence (we follow Bartelmann and Schneider, 2001, eq. 4.12). For the ellipticity maps of redshift slices – produced by the keywords ELLIP_MAP_OUT and ELLIPFITS_PREFIX –, FLASK adopts the weak lensing approximation, $\varepsilon(i) \simeq g(i) + \varepsilon_s(i)$ for the galaxy i. Since the ellipticity value in each pixel would be the average over the ellipticities of the galaxies in that pixel and the noise is assumed Gaussian, the final ellipticity in pixel j is:

$$\varepsilon(j) = \frac{1}{N_{\text{gal}}(j)} \sum_{i}^{N_{\text{gal}}(j)} [g(i) + \varepsilon_{\text{s}}(i)] = g(j) + \frac{\varepsilon_{\text{s}}}{\sqrt{N_{\text{gal}}(j)}}, \tag{4.7}$$

where ε_s is drawn using the ELLIP_SIGMA dispersion, $N_{\rm gal}(j)$ is the number of galaxies in pixel j of that redshift slice and g(j) is the value for the reduced shear in pixel j of that redshift slice. $N_{\rm gal}(j)$ is either given by the galaxy count maps (after Poisson sampling) – if produced in the same simulation run – or by the expected number of galaxies, according to the supplied selection function (see more about this in the description of the ELLIP_MAP_OUT and ELLIPFITS_PREFIX keywords).

Finally, note that the intrinsic ellipticities generated for the catalogue output and for the HEALPIX maps output are, in the current implementation, different and independent processes (the first one follows Eq. 4.6 for each galaxy while the second one follows Eq. 4.7 for each pixel). This means that if you create ellipticity maps from the catalogue you will not get the exact output given by ELLIP_MAP_OUT or ELLIPFITS_PREFIX, unless you set ELLIP_SIGMA ≤ 0 (although they will be statistically equivalent in the weak lensing regime).

Also see the optional keyword REDUCED_SHEAR.

- GALDENSITY: This takes a real number representing the 3D comoving galaxy number density in $(h^{-1}\text{Mpc})^{-3}$. It is only used if SELEC_TYPE: 1 or SELEC_TYPE: 3.
- FIELDS_INFO: This takes a string representing the path to the fields information file described in Sec. 4.1.9.
- CHOL_IN_PREFIX: This takes the character 0 or a string representing the path, including a file prefix, to the files written by the keyword CHOLESKY_PREFIX in a previous FLASK run. If set to 0, the code: takes as input the power spectra $C_{\rm in}(\ell)$ s specified by CL_PREFIX; process it to obtain the associated Gaussian power spectra $C_{\rm g}(\ell)$ s [if DIST: LOGNORMAL, otherwise $C_{\rm g}(\ell) = C_{\rm in}(\ell)$]; build independent covariance matrices for each ℓ ; regularise the matrices if necessary and requested; and perform a Cholesky decomposition to obtain triangular matrices which can be written to files by the CHOLESKY_PREFIX keyword used to generate correlated Gaussian variables. If CHOL_IN_PREFIX is not set to 0, FLASK therefore skips all the processing above and loads its final product the triangular matrices, previously computed into the memory.
- CL_PREFIX: This takes a string that represents the path (including a prefix) to all power spectra $C^{ij}(\ell)$ required to specify the statistical properties of the set of fields listed in the fields information file specified by FIELDS_INFO. Each $C^{ij}(\ell)$ must be in a separate file with two columns $[\ell]$ and $C^{ij}(\ell)$ and must be named with the pattern $[prefix]f[f_i]z[z_i]f[f_j]z[z_j]$. dat. This string is only used if CHOL_IN_PREFIX is set to zero.

It is also possible to pass a single .dat file to CL_PREFIX containing all required $C^{ij}(\ell)$ s. In this case, the file must have the multipole ℓ in the first column and the $C^{ij}(\ell)$ s in the following columns, and the header must be: "# 1 Cl-f[f_i]z[z_i]f[f_j]z[z_j] Cl-f[f_k]z[z_k]f[f_n]z[z_n] Cl-...". The "Cl-" in this header's example can actually be any string (the important part is the $[f_i]$ z[z_i]f[f_j]z[z_j] pattern). The power spectra can be arranjed in any order. If the string passed to CL_PREFIX ends in .dat, FLASK will assume the file is such a table. Otherwise, it will assume it is a prefix for individual $C^{ij}(\ell)$ files.

- ALLOW_MISS_CL: This can be 0 or 1. If 0, FLASK will abort if any required $C^{ij}(\ell)$ is not found. If 1, the code will assume that the missing $C^{ij}(\ell)$ s are zero. This works for cross power spectra but will cause the program to abort if auto power spectra are missing.
- SCALE_CLS: If different from 1.0, all input $C^{ij}(\ell)s$ are multiplied by this factor. When simulating just a single tracer, this can be used as a constant bias term b^2 . The SMOOTH_CL_PREFIX output includes this re-scaling.
- WINFUNC_SIGMA: In case you want to simulate fields that have been convolved (smoothed) in each redshift slice with a 2D Gaussian, you can adjust the Gaussian's standard deviation here (this takes a real number, given in arcmin). The power spectra will be adjusted accordingly. To skip applying this smoothing, set this value to something less than zero.

- APPLY_PIXWIN: To compute the value of a pixel from the map's harmonic coefficients, HEALPIX sums the multipoles weighted by their coefficients (i.e. performs an inverse harmonic transformation) and computes the result at the angular coordinates of the pixel's centre (the pixel value is not the field's average inside the pixel). In case you want the pixel value to be the field's average inside the pixel (which is what people want in most cases), you must apply the HEALPIX window function to the input power spectra; this is done by setting APPLY_PIXWIN to 1. To skip this multiplication, set APPLY_PIXWIN: 0.
- SUPPRESS_L: This takes a real number that represents the scale ℓ_{\sup} at which the input power spectra $C_{\inf}^{ij}(\ell)$ will be exponentially suppressed with index n given by SUP_INDEX. The suppressed power spectra $C_{\sup}^{ij}(\ell)$, used for all subsequent computations and simulations, will be:

$$C_{\sup}^{ij}(\ell) = C_{\inf}^{ij}(\ell) \exp\left[-\left(\frac{\ell}{\ell_{\sup}}\right)^n\right]$$
 (4.8)

To avoid applying this suppression, set either SUPPRESS_L or SUP_INDEX (or both) to something less than zero.

- SUP_INDEX: This takes a real number that represents the index *n* in Eq. 4.8 (see SUPPRESS_L description). You can avoid the use of such suppression by setting this value to a negative number.
- SELEC_SEPARABLE: This specifies if the galaxy selection function is separable between radial and angular parts (1 or 2) or not (0). If separable: the selection function value is the multiplication of the two; if SELEC_SEPARABLE: 1, the keyword SELEC_PREFIX will take a single FITS filename representing the angular selection function as a HEALPIX map that will be used for all galaxy fields and all redshift slices; if SELEC_SEPARABLE: 2, each galaxy field must have its own angular selection function represented by a HEALPIX map, with name given by the prefix specified by SELEC_PREFIX followed by f[fi].fits, where [fi] are numbers "naming" the galaxy fields. In either of these two cases, the keyword SELEC_Z_PREFIX will take a prefix leading to one radial selection function for each galaxy field.

If not separable, the keyword SELEC_PREFIX will take a path with a prefix that should lead to one HEALPIX map in FITS format for each galaxy field and redshift slice, representing the entire selection function (these files must be named by the prefix followed by $f[f_i]z[z_j]$.fits, where $[f_i]$ and $[z_j]$ are the numbers "naming" the entries in the fields information file – see Sec. 4.1.9). In this case, SELEC_Z_PREFIX is ignored.

• SELEC_PREFIX: This takes a string that represents either a path plus a prefix for a bunch of HEALPIX maps in FITS format representing the galaxies selection functions or the filename of a single HEALPIX map, representing the angular part of the selection function (see SELEC_SEPARABLE keyword). It can also be set to 0; in this case, the code works as if the selection function (or the angular selection if SELEC_SEPARABLE: 1 or 2) was equal to one in every pixel. For separable selection functions, this corresponds to a full-sky simulation; for non-separable selection

function, this is just weird. In the current implementation, the selection functions must have the same N_{side} as the one passed to the NSIDE keyword.

- SELEC_Z_PREFIX: This takes a string representing the path plus a prefix for two-column (redshift and radial selection function) text files, one for each galaxy field. This is ignored if SELEC_SEPARABLE: 0. The files can have headers if they start with #, and they have to be named according to the prefix, followed by f[fi].dat, where [fi] is the field number "naming" the field in the fields information file (see Sec. 4.1.9). For proper units, see Sec. 4.1.7. Radial selection functions with negative values in the redshift range being simulated might cause unexpected behaviour in the code.
- SELEC_SCALE: This takes a real number that will serve as a re-scaling of the selection function (the selection function will be multiplied by this value). To use the exact values in the files specified by SELEC_PREFIX and SELEC_Z_PREFIX, set SELEC_SCALE: 1.0. Using negative values here might cause unexpected behaviour in the code.
- SELEC_TYPE: There are two types of selection functions: one (SELEC_TYPE: 0) specifies either the expected number of observed galaxies per unit redshift, per square arcmin (SELEC_SEPARABLE: 1 or 2) or the expected number of observed galaxies per square arcmin for each redshift slice (SELEC_SEPARABLE: 0). The other (SELEC_TYPE: 1) specifies the fraction of existing galaxies that are actually observed at each angular position and redshift. In the latter case, the total existing galaxies is computed from the galaxy density given at GALDENSITY and the comoving volume calculated according to the pixel size (determined by NSIDE), the redshift slice width (set in the fields information file) and the cosmological parameters OMEGA_m, OMEGA_L and W_de. The option SELEC_TYPE: 1 is currently not fully implemented. On top of these two options, the user can specify that the angular part of the selection function is only used for bookkeeping (that is, it does not affect the number of galaxies generated and the simulation is actually full sky) by adding 2 to choice made, leading to the following possible options for SELEC_TYPE: 0, 1, 2 and 3. Currently the bookkeeping option only works for separable selection functions.
- STARMASK: Besides the selection function specified in SELEC_PREFIX, the user can multiply the selection function by a HEALPIX map in FITS file format, passed to this keyword. All selection functions are affected by this angular mask. In the current implementation, this map must have the same $N_{\rm side}$ as the one passed to the NSIDE keyword. To not use this extra angular selection function, the user can set STARMASK: 0.
- EXTRAP_DIPOLE: Many power spectra calculators like CLASS¹ or CAMB SOURCES² write $C(\ell)$ s for $\ell \geq 2$. If this keyword is set to 1, then the dipole $C(\ell = 1)$, if missing, is linearly extrapolated from $C(\ell = 2)$; otherwise, if EXTRAP_DIPOLE: 0 and the dipole is missing, then the dipole is set to zero (NOTE: the monopole is always set to zero).

http://class-code.net/

²http://camb.info/sources

- LRANGE: This takes two integers separated by space representing the minimum ℓ_{min} and maximum ℓ_{max} , respectively, that will be used to generate the associated Gaussian multipoles. They should obey $1 \le \ell_{min} \le \ell_{max} \le \ell_{in}$, where ℓ_{in} is the highest ℓ provided in the input power spectra.
- CROP_CL: The transformation from lognormal to auxiliary Gaussian fields' C_{ℓ} s (Xavier et al., 2016, Eq. 21) needs, in theory, all multipoles ℓ' of the input C_{ℓ} s, up to infinity. In practice, FLASK uses truncated C_{ℓ} s and this might cause the lognormal realizations to follow slightly different C_{ℓ} s at large ℓ . At this stage, there are two options. If CROP_CL: 0, the transformation will be performed using all the multipoles provided in the input C_{ℓ} files. Otherwise, if CROP_CL: 1, FLASK will only use in the transformation the multipoles up to the ℓ_{max} set in the LRANGE keyword. This last option seem to provide better results, but this could vary from case to case. Note that regardless the choice of CROP_CL, the realizations are generated from the multipoles specified in LRANGE.
- SHEAR_LMAX: The shear is derived from the convergence multipoles using the equations from Hu (2000) and the *E*-mode definition from HEALPIX manual. In Gaussian simulations the shear multipoles are derived from the original convergence multipoles used to generate the maps; this is not possible in lognormal simulations since the convergence was generated from multipoles of the associated Gaussian field (a similar argument exists for convergences obtained from density LoS integration). Therefore, to compute the shear from lognormal (or density LoS integration) convergences one needs first to obtain their multipoles. The SHEAR_LMAX keyword takes one integer representing the maximum multipole that will be extracted from the lognormal convergence maps for this purpose (thus it does not affect Gaussian simulations) and the maximum multipole that will be available in shear maps. Using SHEAR_LMAX > NSIDE introduces noise in this transformation.
- NSIDE: This takes an integer representing the HEALPIX N_{side} parameter. The number of pixels N_{pix} used in each redshift slice is $N_{\text{pix}} = 12N_{\text{side}}^2$. Any number can be provided here, although some external applications (e.g. anything based in HEALPY) only accepts powers of 2.
- USE_HEALPIX_WGTS: This keyword states if the code should use (1) or not (0) the HEALPIX weights to perform the map2alm (harmonic transform) operation. The weights are only available for $N_{\text{side}} = 2^n$, where $n \in \mathbb{N}$. If USE_HEALPIX_WGTS: 0, the weights will all be set to unity.
- MINDIAG_FRAC: This keyword takes a real number f. If f > 0, any null diagonal term in the auxiliary (Gaussian) covariance matrices (that can be output by COVL_PREFIX) is set to f times the smallest diagonal term greater than zero in all auxiliary covariance matrices (any ℓ). If this is set to zero or less, nothing happens. This allows for HOMOGENEOUS fields to be simulated along with LOGNORMAL or GAUSSIAN ones.
- BADCORR_FRAC: This takes a real number f. In case some covariance matrix entries lead to forbidden correlations ρ_{ij} ($\rho_{ij} > 1$ or $\rho_{ij} < -1$), FLASK will add this

fractional change to both variances related to the forbidden correlation: $v_i^{\text{new}} = (1+f)v_i^{\text{old}}$ and $v_j^{\text{new}} = (1+f)v_j^{\text{old}}$.

- REGULARIZE_METHOD: In case some associated Gaussian multipoles covariance matrix is non-positive-definite, FLASK can make it positive-definite by changing its entries. There are two methods currently implemented for that, described in Xavier et al. (2016): option REGULARIZE_METHOD: 1 performs an eigendecomposition of the matrix and sets the negative eigenvalues to a new value specified by NEW_EVAL; option REGULARIZE_METHOD: 2 looks for a direction of greatest change in the negative eigenvalues and apply successive distortions (up to REG_MAXSTEPS times) of size given by REGULARIZE_STEP in that direction, until all eigenvalues are positive. You may set REGULARIZE_METHOD: 0 to make FLASK abort in case of non-positive-definite matrices.
- NEW_EVAL: This takes a real number. If REGULARIZE_METHOD is set to 1, covariance matrices negative eigenvalues will be replaced by this value. This value is not used for other REGULARIZE_METHOD options.
- REGULARIZE_STEP: This takes a real number. If REGULARIZE_METHOD is set to 2, this will be the size of the step taken in the direction in the covariance matrix elements space that changes the negative eigenvalues the most. This value is not used for other REGULARIZE_METHOD options.
- REG_MAXSTEPS: This takes an integer number that specifies the maximum amount of steps taken in the covariance matrix elements space when trying to regularise the matrix with REGULARIZE_METHOD: 2. This value is not used for other REGULARIZE_METHOD options.
- ADD_FRAC: If the covariance matrix regularisation fails or if it succeeds but the Cholesky decomposition still fails, FLASK will take the real value passed to this keyword, multiply by the smallest element of the covariance matrix's diagonal and add the result to all diagonal elements of that matrix.
- ZSEARCH_TOL: When building the galaxy catalogue, FLASK will randomly select a redshift inside the galaxy's redshift slice according to the selection function. To do that, it has to find the selection function local maximum inside the redshift bin. The real value passed to ZSEARCH_TOL specifies the precision in redshift to which the maximum is found.
- EXIT_AT: This keyword takes a string that must be either 0 or any other keyword that specifies an output (without the colon, case sensitive). The code will stop right after the point where that output is produced, even if it is not set to be produced. If EXIT_AT: 0, FLASK will run until the end. The output keywords in the example.config file are ordered just like they are produced.
- FITS2TGA: This can take the options: 0, all HEALPIX map outputs remain only in HEALPIX map FITS format; 1, all HEALPIX map outputs also result in a TGA image format version; 2, all HEALPIX map outputs are transformed into TGA images.

- USE_UNSEEN: This keyword takes either 0 or 1. In the first case, all masked pixels in HEALPIX map or text file outputs (e.g. MAPWER_OUT and MAPWERFITS_PREFIX) are set to zero; in the second case, all such pixels are set to HEALPY's UNSEEN value (-1.6375×10^{30}) .
- LRANGE_OUT: This takes to integers separated by space, representing the minimum and maximum ℓ s that will be output in any $C(\ell)$ or $a_{\ell m}$ outputs; this range does not affect calculations, only outputs, and it has to be included in the range set by LRANGE.
- MMAX_OUT: This takes an integer. In $a_{\ell m}$ outputs, the multipoles will all be written out if this is set to a negative number. If this is set to m_{\max} , only $a_{\ell m}$ s with $m \le m_{\max}$ will be written. In the current implementation, m_{\max} must be less than or equal to the minimum ℓ specified in LRANGE_OUT.
- ANGULAR_COORD: This can take three options: 0, all text outputs referring to angular positions will use the polar and azimutal angles θ and ϕ , given in radians, as angular coordinates (HEALPIX style); 1, these outputs will use θ and ϕ in degrees; 2, these outputs will use right ascension and declination in degrees as angular coordinates. This choice does not affect XIOUT_PREFIX and GXIOUT_PREFIX outputs which are always in degrees. For the catalogue output given by CATALOG_OUT, with columns specified by CATALOG_COLS, the choice between right ascension and declination and polar and azimutal angles is overridden by CATALOG_COLS; the choice between radians and degrees for θ and ϕ , performed with ANGULAR_COORD, still applies.
- DENS2KAPPA: If set to 1, FLASK computes a convergence field by integrating the matter density fields along the line of sight (see Xavier et al., 2016, for details). This option requires that density fields in the fields information file are specified in contiguous and ordered redshift bins. The resulting convergence fields are added to the field list and from now on are treated the same way as ordinary convergence fields. If DENS2KAPPA is set to 0, no integration is performed and no new convergence is computed.
 - PLEASE NOTE: FLASK uses the upper edge of the redshift bin as the representative value of z while performing the line of sight integration.
- FLIST_OUT: This keyword takes a string. If anything other than 0, the code treat it as a filename and writes the list of fields in use by the code to this file.
- SMOOTH_CL_PREFIX: Path plus prefix for the power spectra output, after re-scaling the input $C^{ij}(\ell)$ s by SCALE_CLS and applying the Gaussian window function according to WINFUNC_SIGMA, the HEALPIX pixel window function according to APPLY_PIXWIN and the exponential suppression according to SUPPRESS_L and SUP_INDEX keywords. Set to 0 for no output.
 - If the string passed to SMOOTH_CL_PREFIX ends in .dat, all $C^{ij}(\ell)$ s will be written to a single file instead of individual files.
- XIOUT_PREFIX: Path with prefix for angular correlation functions $\xi^{ij}(\theta)$, written as two column (angle θ in degrees and $\xi^{ij}(\theta)$) text files. Currently it can only be

- calculated if DIST: LOGNORMAL and there is no option of outputting all $\xi^{ij}(\theta)$ to a single .dat file. Set to 0 for no output.
- GXIOUT_PREFIX: Path, including a prefix, for angular correlation functions $\xi_g^{ij}(\theta)$ of the associated Gaussian fields, written as two column (angle θ in degrees and $\xi_g^{ij}(\theta)$) text files. This is only calculated if the input fields are lognormal. Set to 0 for no output. Currently there is no option of outputting all $\xi^{ij}(\theta)$ to a single .dat file.
- GCLOUT_PREFIX: Prefix (including path) for angular power spectra $C_{\rm g}^{ij}(\ell)$ of the associated Gaussian fields. This is only calculated if DIST: LOGNORMAL. Set to 0 for no output. Currently there is no option of outputting all $\xi^{ij}(\theta)$ to a single .dat file.
- COVL_PREFIX: Path plus prefix for the Gaussian $a_{\ell m}^i$ s covariance matrices [for a fixed ℓ , $C_{\rm g}^{ij}(\ell)$ is the element (i,j) of the covariance matrix]. Set to 0 for no output.
- REG_COVL_PREFIX: Path with prefix for the covariance matrices that would be output by COVL_PREFIX but after being regularised according to the choice in REGULARIZE_METHOD. Set to 0 for no output.
- REG_CL_PREFIX: Prefix (including path) for the regularised input $C^{ij}(\ell)$ s. In case DIST: LOGNORMAL, the $C^{ij}(\ell)$ s output here are for the lognormal fields, not for the auxiliary Gaussian fields. For no output, set this keyword to 0. If the string passed to this keyword ends in .dat, all regularized $C^{ij}(\ell)$ s are written to a single file. Note that the order the $C^{ij}(\ell)$ s appear in this file will follow the order in the fields information file passed to FIELDS_INFO, not the order in the file passed to CL_PREFIX.
- CHOLESKY_PREFIX: Path plus prefix for the outcome of the Cholesky decomposition as implemented by the *GNU Scientific Library* (GSL).³ Set to 0 for no output. These files can be passed as input to FLASK by using the keyword CHOL_IN_PREFIX.
- AUXALM_OUT: Filename (with path) for the table with multipoles coefficients $a^i_{\ell m}$ of every associated Gaussian field and redshift slice i being simulated. Since the fields are real, only $a^i_{\ell m}$ with $m \ge 0$ are written. Set to 0 for no output.
- RECOVAUXCLS_OUT: Filename (with path) for the table with $C^{ij}(\ell)$ s recovered from the realized $a^i_{\ell m}$ s of the associated Gaussian fields (see AUXALM_OUT keyword). The computation is performed according to Eq. 4.1. Set to 0 for no output.
- AUXMAP_OUT: Filename (with path) for a text table containing the pixel's centre angular coordinates and the values at that point of every associated Gaussian field at every redshift slice being simulated. Set to 0 for no output.
- DENS2KAPPA_STAT: This can be set to 0 for no output, to 1 for output on the screen, or to a filename in case the user wants the output to be written to a file. The output

³ Check http://www.gnu.org/software/gsl/manual/html_node/Cholesky-Decomposition.html for details.

is a table with statistical properties of the convergence obtained from density LoS integration. This information is only produced if DENS2KAPPA: 1.

- MAP_OUT: Path plus filename for a text table containing the pixel's centre angular coordinates and the values at that point of every field (Gaussian or lognormal, according to DIST) at every redshift slice being simulated. This does not include the selection function nor noise apart from cosmic variance. Set to 0 for no output.
- MAPFITS_PREFIX: Prefix (including path) for a HEALPIX map FITS file for each simulated field and redshift slice. The output format can be altered by FITS2TGA. This does not include the selection function nor noise apart from cosmic variance. Set to 0 for no output.
- RECOVALM_OUT: Path plus filename for a text table of multipole coefficients $a^i_{\ell m}$ recovered, using the map2alm HEALPIX function, from the maps that can be output by MAP_OUT and MAPFITS_PREFIX. Set to 0 for no output.
- RECOVCLS_OUT: Path plus filename for a text table of power spectra $C^{ij}_{\rm rec}(\ell)$ recovered from the maps that can be output by MAP_OUT and MAPFITS_PREFIX. In other words, $C^{ij}_{\rm rec}(\ell)$ is the average over m of $a^i_{\ell m}a^{j*}_{\ell m}$, where $a^i_{\ell m}$ can be output by RECOVALM_OUT (see Eq. 4.1). Set to 0 for no output.
- SHEAR_ALM_PREFIX: Prefix (including path) for files containing the weak lensing shear E-mode multipole coefficients $a_{\ell m}^i$, one for each lensing field and redshift slice. Set to 0 for no output.
- SHEAR_FITS_PREFIX: Prefix (including path) for HEALPIX maps of weak lensing attributes, obtained from lensing $a_{\ell m}s$ (*E*-modes that can be output by SHEAR_ALM_PREFIX) by the HEALPIX function alm2map_spin. These FITS files contain three columns: convergence κ and shear components γ_1 and γ_2 . This does not include the selection function nor noise apart from cosmic variance. Set to 0 for no output.
- SHEAR_MAP_OUT: Path plus filename for a text table containing the pixel's centre angular coordinates and the values at that point of the two shear components γ_1 and γ_2 of every weak lensing field at every redshift slice. This does not include the selection function nor noise apart from cosmic variance. Set to 0 for no output.
- MAPWER_OUT: Path plus filename for a text table containing the pixel's centre angular coordinates and the values at that point of the fields after applying the selection function and sampling (see POISSON keyword) the galaxy density fields; that is, the values are the number of galaxies in each pixel in each redshift slice (i.e. in each cell). In the current implementation, convergence fields do not get any noise contribution apart from cosmic variance and are masked out according to the angular selection function (see Sec. 4.1.7 for possible exceptions). Set to 0 for no output.
- MAPWERFITS_PREFIX: Prefix (including path) for the HEALPIX maps version of the MAPWER_OUT output, one file per field per redshift slice. Set to 0 for no output.

• ELLIP_MAP_OUT: This keyword takes a path plus a filename for a text table describing the ellipticity inside pixels centered at the angular coordinates specified in the file. The file will contain two columns (the two components of the complex ellipticity) for each galaxy field in each redshift slice where lensing fields are also specified. The ellipticity in each pixel is given by Eq. 4.7, where $N_{\rm gal}(j)$ is given by the Poisson sampled number (or the expected number if POISSON: 0, or Gaussian sampled number if POISSON: 2) of galaxies (of that type, if simulating more than one tracer) in the pixel; if $N_{\rm gal}(j) \leq 0$, the pixel is masked out (i.e. it gets the value specified by the USE_UNSEEN keyword).

If there are no galaxy fields being simulated, FLASK will require that a selection function is assigned to the lensing field and this will be assumed to be the sources' selection function. Since in this case the sources are not Poisson sampled, $N_{\rm gal}(j) = \langle N_t(i,j) \rangle = \bar{n}_t(i,j)\Delta\Omega$ (see Sec. 4.1.7). Pixels were the selection function is equal to or less than zero are masked out. You can set this keyword to 0 for no output.

- ELLIPFITS_PREFIX: This keyword takes a path plus a prefix for a set of HEALPIX maps that are written out, each one describing an ellipticity field for a certain tracer and at a certain redshift, just like the columns described in the ELLIP_MAP_OUT keyword. Each .fits file contains three maps: the last two are the two components of the ellipticity for that tracer at that redsfhit and the first one is the same convergence map as the one generated by the MAPWER_OUT keyword, at the same redshift. You can set this keyword to 0 for no output.
- CATALOG_OUT: Path plus filename for a galaxy catalogue in *binary* FITS or compressed FITS formats, chosen accordingly to the filename extension: .fits or .fits.gz, respectively. Each row is one galaxy from the map described in MAPWER_OUT and the columns are chosen by the user using the CATALOG_COLS keyword. Set to 0 for no output. Also see the optional keyword CAT32BIT.
- CATALOG_COLS: This takes as input everything in the same line of the configuration file after it, and it specifies the columns to be included in the galaxy catalogue output by CATALOG_OUT. They can be:
 - theta, the polar angle θ of the galaxy position given in units according to ANGULAR_COORD, randomly sampled inside the corresponding pixel;
 - phi, the azimutal angle ϕ of the galaxy position given in units according to ANGULAR_COORD, randomly sampled inside the corresponding pixel;
 - ra, the right ascension given in degrees;
 - dec, the declination given in degrees (the choice of angular coordinates is exclusive, one cannot mix different coordinate systems in the catalogue, e.g. dec and phi or dec and theta);
 - z, the galaxy's redshift, which is randomly sampled inside the corresponding cell according to the selection function;
 - r, the comoving distance, given in h^{-1} Mpc, associated to the galaxy's redshift

z above, according to the formula:

$$r = \frac{c}{H_{100}} \int_0^z \frac{\mathrm{d}z'}{\sqrt{\Omega_{\mathrm{m}}(1+z')^3 + \Omega_{\mathrm{k}}(1+z')^2 + \Omega_{\mathrm{L}}(1+z')^{3(1+w_{\mathrm{de}})}}},$$
 (4.9)

where: $H_{100} = 100 \,\mathrm{m\,s^{-1}\,Mpc^{-1}}$, $\Omega_{\rm k} = 1 - \Omega_{\rm m} - \Omega_{\rm L}$; and $\Omega_{\rm m}$, $\Omega_{\rm L}$ and $w_{\rm de}$ are given by the keywords OMEGA_m, OMEGA_L and W_de. Therefore, the interpretation of r depends on what is being simulated, e.g. if the input power spectra includes redshift space distortions, r will be the distance in redshift space.

- galtype, i.e. the field's name as in the fields information file, see Sec. 4.1.9;
- kappa, the convergence κ at the corresponding cell (pixel and redshift slice);
- gamma1, the first component of the shear, γ_1 , at the corresponding cell;
- gamma2, the second component of the shear, γ_2 , at the corresponding cell;
- ellip1, the first component of the ellipticity of the galaxy ε_1 , given by Eq. 4.6;
- ellip2, the second component of the ellipticity of the galaxy ε_2 , given by Eq. 4.6;
- pixel, the HEALPIX map pixel number of the corresponding cell;
- maskbit, returns a sum of the following integers: 1 if the galaxy would be removed by the angular selection function, i.e., if the angular selection function value at the corresponding pixel is zero or less; 2 if the galaxy would be removed by the star mask given by STARMASK, i.e., if the star mask value at the corresponding pixel is zero or less; 4 if the angular selection function value s obeys 0 < s < 1 (only if the selection function is separable); 8 if the star mask value s obeys s of s of s of s of the angular selection function value s is s only if the selection function is separable); and 32 if the star mask value s is s of s

The column names have to be separated by spaces and they can appear in any number (no repeated columns, though) and order.

- CAT_COL_NAMES: (Optional) This keyword allows one to provide a custom header name for each of the columns in the galaxy catalogue that are requested through the keyword CATALOG_COLS. The number of header names provided here should match the number of columns requested through CATALOG_COLS and their sequence must also match. If the keyword CAT_COL_NAMES is missing in the configuration file, FLASK will assign the columns defined through the CATALOG_COLS keyword as the column names.
- CAT32BIT: (Optional) The galaxy catalogue is always written in binary format and this keyword allows the user to specify whether the floating point numbers should be written in 32-bit or 64-bit format. Set the value to be 1 to write in 32-bit and 0 for 64-bits. If this keyword is missing from the configuration file, and if the

keyword CATALOG_OUT is present, FLASK will assume a default value of 0 (64-bits) for the keyword CAT32BIT, since it is the higher precision (although slower) option. The 32-bit option produces sufficient precision for most purposes, so one should seriously consider it in order to save hard disk space and speed up FLASK.

• REDUCED_SHEAR: (Optional) In most cases, the reduced shear is used when calculating the observed ellipticities (Equations (4.6) and (4.7)). However, if the user wishes to use shear when calculating the observed ellipticities, this keyword should be set to a value of 0. If this keyword is missing from the configuration file, a default value of 1 (reduced shear) will be assumed (Equations (4.6) and (4.7) used).

If this keyword is set to 0, i.e. shear chosen instead of reduced shear, then Eqs. (4.6) and (4.7) are modified as

$$\varepsilon = \begin{cases} \varepsilon_{s} + \gamma, & |g| \leq 1; \\ \frac{1 + g\varepsilon_{s}^{*}}{\varepsilon_{s}^{*} + g^{*}}, & |g| > 1; \end{cases}$$

$$(4.10)$$

$$\varepsilon(j) = \frac{1}{N_{\text{gal}}(j)} \sum_{i}^{N_{\text{gal}}(j)} \left[\gamma(i) + \varepsilon_{\text{s}}(i) \right] = \gamma(j) + \frac{\varepsilon_{\text{s}}}{\sqrt{N_{\text{gal}}(j)}}, \tag{4.11}$$

In addition, while implementing Eqs. (4.10) and (4.11), FLASK imposes the restriction that the maximum value of shear (γ) that can be encountered is 0.1. Hence, intrinsic elipticities (ε_s) are allowed to be only up to 0.9. Also note that for |g| > 1, FLASK will always use the reduced shear even if the keyword REDUCED_SHEAR is set to 0.

4.1.9 Fields information file

The fields information file is a text file that informs FLASK the fields and redshift slices it should simulate, along with their properties. In the current implementation, these files can have any number of lines serving as headers (that should always start with a #). Empty lines can also appear before the tabular data, but they cannot contain spaces. Once the tabular data appears, you should stick to it. The file can end at the last data line or with an empty line (no spaces allowed). An example of such file is given in Fig. 4.2.

# Field number, z bin number, mean, shift, field type, zmin, zmax # Types: 1-galaxies 2-lensing								
	1	1	0.0000	1.0000	1	0.2500	0.3500	
	1	2	0.0000	1.0000	1	0.3500	0.4500	
	1	3	0.0000	1.0000	1	0.4500	0.5500	
	2	1	0.0000	0.0050	2	0.2500	0.3500	
	2	2	0.0000	0.0084	2	0.3500	0.4500	
	2	3	0.0000	0.0126	2	0.4500	0.5500	

Figure 4.2: Example of a fields information file with two fields (one of type *galaxy* or *matter density* and the other of type *weak lensing convergence*) in three redshift slices. The column order is summarised in the header.

The fields information file columns must be, in this order:

- An arbitrary natural number "naming" the field (for multi-tracer simulations, they can identify different galaxy populations).
- An arbitrary natural number "naming" the redshift slice.
- The fields mean value at that redshift slice, usually zero (for density contrast and convergence, for instance);
- The fields shift parameter, if the field is lognormal (in case of a Gaussian simulation, this column still have to be present but it will be ignored).
- The field type, which determines how the field is treated inside the code. In the current implementation, this can be either 1 (CMB or gas temperature, matter density or matter density tracers like galaxies, quasars, etc.) or 2 (weak lensing convergence). These types affect how FLASK deals with selection functions, noise and field transformations. For details, one can look for flensing and fgalaxies in the code using the command grep.
- The lower boundary of the redshift slice;
- and the upper boundary of the redshift slice. The redshift slices may overlap, have any size and ordering (unless you are integrating the density, see the DENS2KAPPA keyword in Sec. 4.1.8). In the current implementation, these are only used in the density LoS integration controlled by the DENS2KAPPA, to Poisson sample the density fields or to compute shape noise for galaxy ellipticity maps according to Eq. 4.7; in all cases, the redshift slice is assumed to be a top-hat redshift window function. If you are not performing these operations, these redshift boundaries are irrelevant and the slices can present arbitrary redshift window functions (e.g. Gaussians), according to the power spectra provided as input.

To simulate the fields and redshift slices mentioned in a fields information file, FLASK requires their auto power spectra and all cross power spectra (unless the keyword ALLOW_MISS_CL is set to 1). Each power spectrum has to be in a file with prefix given by the keyword CL_PREFIX followed by $f[f_i]z[z_i]f[f_j]z[z_j]$. dat, where $[f_i]$ and $[z_i]$ are the numbers (no zero-padding allowed) in the first and second columns of the fields information file. For instance, if the configuration file have CL_PREFIX: data/testCl- and FIELDS_INFO referring to the file in Fig. 4.2, FLASK will look for the files:

```
data/testCl-f1z1f1z1.dat
                          data/testCl-f2z1f1z1.dat
data/testCl-f1z1f1z2.dat
                          data/testCl-f2z1f1z2.dat
data/testCl-f1z1f1z3.dat
                          data/testCl-f2z1f1z3.dat
data/testCl-f1z1f2z1.dat
                          data/testCl-f2z1f2z1.dat
data/testCl-f1z1f2z2.dat
                          data/testCl-f2z1f2z2.dat
data/testCl-f1z1f2z3.dat
                          data/testCl-f2z1f2z3.dat
data/testCl-f1z2f1z1.dat
                          data/testCl-f2z2f1z1.dat
data/testCl-f1z2f1z2.dat
                          data/testCl-f2z2f1z2.dat
data/testCl-f1z2f1z3.dat
                          data/testCl-f2z2f1z3.dat
data/testCl-f1z2f2z1.dat
                          data/testCl-f2z2f2z1.dat
data/testCl-f1z2f2z2.dat
                          data/testCl-f2z2f2z2.dat
data/testCl-f1z2f2z3.dat
                          data/testCl-f2z2f2z3.dat
data/testCl-f1z3f1z1.dat
                          data/testCl-f2z3f1z1.dat
data/testCl-f1z3f1z2.dat
                          data/testCl-f2z3f1z2.dat
data/testCl-f1z3f1z3.dat
                          data/testCl-f2z3f1z3.dat
data/testCl-f1z3f2z1.dat
                          data/testCl-f2z3f2z1.dat
data/testCl-f1z3f2z2.dat
                          data/testCl-f2z3f2z2.dat
data/testCl-f1z3f2z3.dat
                          data/testCl-f2z3f2z3.dat
```

However, since the cross power spectra are symmetric (testCl-f[f_i]z[z_i]f[f_j]z[z_j].dat = testCl-f[f_i]z[z_i]f[f_i]z[z_i].dat), FLASK only requires 21 of the files listed above.

In case you use CLASS⁴ (Blas et al., 2011; Dio et al., 2013) or CAMB SOURCES⁵ (Challinor and Lewis, 2011) to compute the input power spectra, it is possible to use the Python scripts called class2info.py and camb2info.py in FLASK's src/scripts folder to create the fields information file corresponding to CLASS and CAMB SOURCES input (.ini) files. See Sec. 4.2 and the scripts' docstring for more information.

Since March 2019, it is also possible to pass a single file ending by .dat to CL_PREFIX containing all required power spectra. See Sec. 4.1.10 for more details.

4.1.10 Angular power spectra files

Apart from the distribution's PDF – determined by the DIST keyword in the configuration file – and the fields mean and shift parameters in the fields information file, all statistical properties of the simulated fields are fixed by the input angular power spectra $C_{\rm in}^{ij}(\ell)$, including their cross-correlations. All characteristics such as: tracer biases with respect to matter density; redshift space distortions; galaxy intrinsic alignments; integrated Sachs-Wolfe effect; tracer evolution with redshift; and magnification bias can be included in the simulations by providing the appropriate $C_{\rm in}^{ij}(\ell)$ with such information encoded in them. The step of computing these power spectra is not part of FLASK and is left to the user. Some public codes available to perform such calculations are: CLASS⁶ (Blas et al., 2011; Dio et al., 2013) and CAMB SOURCES⁷ (Challinor and Lewis, 2011).

In the current implementation, the $C_{\rm in}^{ij}(\ell)$ s can be passed to FLASK in two ways:

⁴http://class-code.net/

⁵http://camb.info/sources

⁶http://class-code.net/

⁷http://camb.info/sources

- As individual files: these must be named as explained in 4.1.9 and must have two columns: ℓ and $C_{\rm in}^{ij}(\ell)$ (no headers allowed here). The $C_{\rm in}^{ij}(\ell)$ is the power spectra itself and not something like $l(l+1)/(2\pi)\cdot C_{\rm in}^{ij}(\ell)$. They are interpolated by the code so it is not necessary to specify them at every ℓ or at integer ℓ s. For the user's convenience, Python scripts called prepClassInput.py and prepCambInput.py are available in FLASK's src/scripts folder that can translate CLASS and CAMB SOURCES output power spectra into FLASK input power spectra. See Sec. 4.2 and the scripts' docstring for more information.
- As a table in a single file (ending by .dat): the first column must be ℓ and the following ones the $C_{\rm in}^{ij}(\ell)$ s. In the example given by Fig. 4.2, we could have something like CL_PREFIX: data/testCl.dat in the configuration file, and this file would contain 22 columns [the first one for ℓ and the remaining ones for the 21 required $C^{ij}(\ell)$ s]. This file must have a header starting with #, followed by column labels separated by spaces. The labels of the power spectra columns must contain the pattern $[f_i]\mathbf{z}[z_i]\mathbf{f}[f_j]\mathbf{z}[z_j]$ indicating to which field and redshift slice pairs they correspond to.

4.2 Auxiliary codes

There are several smaller routines available in FLASK's directory that can help the user prepare its inputs and visualise or organise its outputs. Here we list the most important of them. More information can be found on their docstrings.

4.2.1 Dens2KappaCls

This is a C++ code compiled to the bin sub-directory that takes the input power spectra and configuration file that would be used by FLASK and compute the expected power spectra that would be recovered from convergence computed by integrating simulated lognormal densities along the line of sight (i.e., this code computes the red solid lines in Fig. 15 of Xavier et al. (2016).

The Dens2KappaCls usage is similar to that of FLASK: you run it by invoking the executable followed by the path to the configuration file, followed by keywords you want to change. The difference is that the last parameter passed to Dens2KappaCls must be the output files prefix for the $C(\ell)$ s of the convergence obtained from density LoS integration, for instance:

Dens2KappaCls example.config NSIDE: 128 output/kappaCl-

Although this code takes the same configuration file as FLASK and will complain if any keyword is missing, the only keywords it actually uses are: FIELDS_INFO, CL_PREFIX, ALLOW_MISS_CL, OMEGA_m, OMEGA_L and W_de (therefore, changing NSIDE in the example above is a bit silly).

In the current version, Dens2KappaC1s does not apply any window function or suppression to the input $C(\ell)$ s before integrating them. In case you want to compare its output with recovered $C(\ell)$ s from FLASK and have applied any of these changes to the FLASK input power spectra, you should use the SMOOTH_CL_PREFIX keyword in FLASK to output files to be used as input here.

4.2.2 GenStarMask

This routine, written in C++, creates a full-sky random star mask with parameters given by the user and then outputs it to a HEALPIX map in FITS format. The parts without stars have value 1 and the parts with stars (which are modelled as disks) have value 0. If necessary, these values can be changed in the source code by redefining the StarValue and EmptyValue variables.

GenStarMask takes 6 inputs, in this order: a integer used as seed for random numbers; the $N_{\rm side}$ HEALPIX resolution parameter; a minimum angular radius for the stars $r_{\rm min}$, given in arcmin; a maximum angular radius for the stars $r_{\rm max}$, given in arcmin; the sky fraction to be covered by stars; and the filename for the output.

The stars (modelled as disks) are distributed homogeneously on the sky, and the natural logarithmic of the disk radius are homogeneously sampled between $\ln(r_{\min})$ and $\ln(r_{\max})$. The stars can be superimposed and are generated until the fraction of pixels covered by stars is greater than the value specified in the input.

4.2.3 camb2info.py

This Python script takes a CAMB SOURCES input file and creates a FLASK fields information file. It takes as input, in this order: the CAMB SOURCES .ini filename and the output filename.

There are three methods for computing the shift parameter for convergence: a table read from a file which is interpolated; the formula from Hilbert et al. (2011); and a formula computed from FLASK density line of sight integration. The latter is currently used (the others are commented out in the script). To generate the zmin and zmax columns in the fields information file, this routine uses the redshift_sigma entry in the CAMB SOURCES .ini file as half of the redshift bin width. Note that CAMB SOURCES assumes, by default, that the redshift bins have Gaussian selection functions. If necessary, the user must modify CAMB SOURCES to use top-hat redshift bins.

4.2.4 class2info.py

This Python script works in the same way as camb2info.py but for CLASS input (.ini) files (it uses the selection_width keyword as half of the redshift bin width).

4.2.5 ChangeMapResolution.py

This Python script gets a HEALPIX map in FITS format, changes its resolution (given by $N_{\rm side}$) and write the new map to another FITS file. Its inputs are, in this order: the input map, $N_{\rm side}$ and the output map. When increasing the resolution, the pixels inside the original pixel all get the same value as the original one; and when decreasing the resolution, the new pixel takes the average value of the original pixels inside it.

4.2.6 prepCambInput.py

This Python script translates the $C(\ell)$ s written by CAMB SOURCES to the output file with scalCovCls.dat suffix to the $C(\ell)$ files used by FLASK as input: besides partitioning

the $C(\ell)$ s into separate and appropriately named files (see Sec. 4.1.10), it removes the $\ell(\ell+1)/2\pi$ factors to return the pure $C(\ell)$ s.

Since CAMB SOURCES output files currently have no headers, this script requires as input the fields information file created by camb2info.py. Therefore, its input parameters are, in this order: the CAMB SOURCES $C(\ell)$ s file (with suffix scalCovCls.dat); the fields information file; and the prefix for the output $C(\ell)$ s.

4.2.7 prepClassInput.py

This Python script is the analogous of prepCambInput.py but for CLASS output $C(\ell)$ s. There are two more differences from prepCambInput.py. First, since CLASS output files have headers, this script does not require a fields information file and only take two input parameters, in this order: the CLASS $C(\ell)$ s file (with cl.dat suffix); and the prefix for the output $C(\ell)$ s. Second, since CLASS outputs lensing potential $C(\ell)$ s instead of convergence $C(\ell)$ s, this script converts the former into the latter (and also performs a similar transformation for the cross angular power spectra) using the factors described in Hu (2000). Check the script code for more information.

4.2.8 summarizeData.py

This Python script takes a list of N files (which can be specified using wildcards like *) that must all have the same shape (basically a table with the same number of columns and rows) and headers starting with # (or no headers) and compute the average of each entry x_{ij} over all files. For example, the table element \bar{x}_{ij} in the output file is given by:

$$\bar{x}_{ij} = \frac{1}{N} \sum_{n=1}^{N} x_{n,ij}.$$
 (4.12)

This script also computes the standard deviation in an analogous fashion. Therefore, the two outputs (the average file and the standard deviation file) have the same shape as the input. This script input parameters are, in this order: the filename for the average output; the filename for the standard deviation output; and the files to be averaged over (which can be specified using wildcards).

4.2.9 ViewMap.py

This Python script takes as arguments filenames of HEALPIX maps saved as FITS files and plots them in Mollweide projection. Each map is opened in a different window and can be saved under different formats.

4.2.10 z-range2camb-ini.py

This Python script prints to stdout the part of CAMB SOURCES .ini file that describes the redshift windows for the galaxy counts and lensing. It takes as input a redshift range $[z_{\min}, z_{\max}]$ and the number of redshift bins N, in this order, and splits the range in contigous N bins that span the range. Currently it only outputs counts entries with unit bias and $\frac{\mathrm{d}}{\mathrm{dm}} \log_{10} N = 0$.

4.2.11 config-changes.sh

This BASH script prints to stdout what changes you must make in your configuration file to make it compatible with a certain version of FLASK. The idea is that as FLASK is updated, keywords might be added or removed, and this scripts helps the user to make previous configuration files compatible with new versions of the code by comparing them to the new example.config file. Check the script comments for more information.

4.2.12 joinClFiles.py

This Python script takes as input an arbitrary number of individual power spectra files following FLASK's naming convention and put them into a single file, whose columns will be named 1 (for the multipole numbers ℓ) and the same as the original filenames (for the power spectra columns), without the directories and .dat extension. It takes as input the individual $C^{ij}(\ell)$ files and the output file (that must be the last input passed to this script).

4.2.13 MathMap.py

This Python script allows mathematical operations to be made with HEALPIX maps with the same $N_{\rm side}$ directly from the command line. The operations are made pixel-wise. It allows for addition, subtraction, multiplication, division and exponentiation, as well as parenthesis. For more information, check its docstring by running the script without any arguments. An arbitrary number of maps can be operated on, and they are referred to by their filenames. It is recommended to always separate all terms passed to the script (operators, parenthesis and filenames) by spaces, to avoid confusion. Note that parenthesis, multiplication and exponentiation are referred to by tailored symbols.

4.2.14 config_to_ini.py

This script converts a configuration file given in the .config format to the one in .ini format.

Bibliography

- Bartelmann, M. and Schneider, P. (2001). Weak gravitational lensing. *Physics Reports*, 340:291. astro-ph/9912508.
- Blas, D., Lesgourgues, J., and Tram, T. (2011). The cosmic linear anisotropy solving system (class) ii: Approximation schemes. *Journal of Cosmology and Astroparticle Physics*, 1107:034. arXiv:1104.2933.
- Challinor, A. and Lewis, A. (2011). The linear power spectrum of observed source number counts. *Physical Review D*, 84:043516. arXiv:1105.5292.
- Dio, E. D., Montanari, F., Lesgourgues, J., and Durrer, R. (2013). The CLASSgal code for relativistic cosmological large scale structure. *Journal of Cosmology and Astroparticle Physics*, 1311:044. arXiv:1307.1459.
- Hilbert, S., Hartlap, J., and Schneider, P. (2011). Cosmic shear covariance: The lognormal approximation. *Astronomy & Astrophysics*, 536:A85. arXiv:1105.3980.
- Hu, W. (2000). Weak lensing of the CMB: A harmonic approach. *Physical Review Letters D*, 62:043007. astro-ph/0001303.
- Landy, S. D. and Szalay, A. S. (1993). Bias and variance of angular correlation functions. *The Astrophysical Journal*, 412(1):64. doi:10.1086/172900.
- Xavier, H. S., Abdalla, F. B., and Joachimi, B. (2016). Improving lognormal models for cosmological fields. *Monthly Notices of the Royal Astronomical Society*, 459:3693. arXiv:1602.08503.