





Copyright © 2011 EMC Corporation. All rights reserved.

EMC believes the information in this publication is accurate as of its publication date. The information is subject to change without notice.

THE INFORMATION IN THIS PUBLICATION IS PROVIDED "AS IS." EMC CORPORATION MAKES NO REPRESENTATIONS OR WARRANTIES OF ANY KIND WITH RESPECT TO THE INFORMATION IN THIS PUBLICATION, AND SPECIFICALLY DISCLAIMS IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.

Use, copying, and distribution of any EMC software described in this publication requires an applicable software license

For the most up-to-date listing of EMC product names, see EMC Corporation Trademarks on EMC.com

All other trademarks used herein are the property of their respective owners.

Contents - Greenplum Database 4.1 Load Tools for Unix

Chapter 1: Installing the Greenplum Load Tools	
Running the Load Tools Installer	
About Your Installation	
Configuring the Command-Line Load Tools	
Additional Connection Environment Variables	
Enabling Greenplum Database for Remote Client Connections	
Next Steps	
Appendix A: Load Tools Referencegpfdist	4
gpload	8
Appendix B: SQL Command Reference	19
SQL Syntax Summary	
	4

Table of Contents 1

1. Installing the Greenplum Load Tools

This section contains information for installing the Greenplum data loading programs on your client machine and for enabling Greenplum Database to accept remote client connections:

- Running the Load Tools Installer
- Next Steps

Running the Load Tools Installer

The Greenplum Database load tools installer installs the following data loading tools:

- Greenplum parallel file distribution program (gpfdist)
- Greenplum data loading utility (gpload)

To install the Greenplum Database load tools

- **1.** Download the appropriate greenplum-loaders-4.1.x.x-PLATFORM.bin.zip installer package for your platform from http://gpn.greenplum.com. The currently supported platforms are RedHat Linux 32-bit, RedHat Linux 64-bit, and Solaris 64-bit.
- **2.** Unzip the installer:

```
unzip greenplum-loaders-4.1.x.x-PLATFORM.bin.zip
```

3. Run the installer:

```
/bin/bash greenplum-loaders-4.1.x.x-PLATFORM.bin
```

4. The installer will prompt you to accept the license agreement and to provide an installation path. For the installation path, be sure to enter an absolute path if you choose not to accept the default location (for example,

```
/mydir/gp-loader-tools). The load tools are installed into /usr/local/greenplum-loaders-4.1.x.x by default.
```

About Your Installation

Your Greenplum Database load tools installation contains the following files and directories:

- bin data loading command-line tools and library files (gpfdist and gpload)
- **docs** documentation files
- greenplum loaders path.sh environment variables

Configuring the Command-Line Load Tools

As a convenience, a greenplum_loaders_path.sh file is provided in your load tools installation directory following installation. It has the following environment variable settings:

GREENPLUM_LOADERS_HOME — The installation directory of the Greenplum Database load tools

PATH — The path to the data loading command-line utilities.

LD LIBRARY PATH — The path to additional Python library files needed for gpload.

You can source this file in your user's startup shell profile (such as .bashrc or .bash profile).

For example, you could add a line similar to the following to your chosen profile files (making sure the right install path is used):

source

/usr/local/greenplum-loaders-4.1.x.x/greenplum loaders path.sh

After editing the chosen profile file, source it as the correct user to make the changes active. For example:

source ~/.bashrc

Additional Connection Environment Variables

The Greenplum load tools require several connection parameters in order to be able to connect to a Greenplum Database instance. In order to save some typing on the command-line, you can create the following environment variables in your preferred profile file (such as .bashrc).

- **PGDATABASE** The name of the default Greenplum database to connect to.
- **PGHOST** The Greenplum master host name or IP address.
- **PGPORT** The port number that the Greenplum master instance is running on.
- **PGUSER** The default database role name to use for login.

Enabling Greenplum Database for Remote Client Connections

In order for Greenplum Database to be able to accept remote client connections, you must configure your Greenplum Database master so that connections are allowed from the client hosts and database users that will be connecting to Greenplum Database. This section lists the high-level steps. For more detailed information, see the *Greenplum Database Administrator Guide*.

To enable remote client connections

1. Edit the postgresql.conf file of the Greenplum master instance and modify the listen_addresses setting to include the TCP/IP addresses or hostnames of the remote clients. The special entry * corresponds to all hosts. For example:

```
listen_addresses = 'localhost', 'remotehost1', 'remotehost2'
listen_addresses = '*'
```

- **2.** Next you must make sure that the pg_hba.conf file of the Greenplum master is correctly configured to allow connections from the users to the database(s) using the authentication method you want. See the section on *Editing the pg_hba.conf File* in the *Greenplum Database Administrator Guide* for details. Make sure the authentication method you choose is supported by the client tool you are using.
- **3.** Restart Greenplum Database after making these configuration changes.
- **4.** Also make sure that the databases and roles you are using to connect exist in the system and that the roles have the correct priviliges to the database objects.

Next Steps

Refer to the load tool reference documentation for further instructions:

- Greenplum Load Tools See "Load Tools Reference" on page 4.
- Greenplum Database SQL Syntax See "SQL Command Reference" on page 19.

Next Steps 3

A. Load Tools Reference

This chapter describes the data loading tools provided with this release. They all require certain connection information such as the Greenplum Database master host name, port, database name, and role name. These can be configured using environment variables. See "Configuring the Command-Line Load Tools" on page 2.

The following tools are provided:

- Greenplum parallel file distribution program (gpfdist)
- Greenplum data loading utility (gpload)

Load Tools Reference 4

gpfdist

Serves data files to or writes data files out from Greenplum Database segments.

Synopsis

```
gpfdist [-d directory] [-p http_port] [-l log_file] [-t timeout]
[-m max_length] [-v | -V]
gpfdist --version
```

Description

gpfdist is Greenplum's parallel file distribution program. It is used by readable external tables and gpload to serve external table files to all Greenplum Database segments in parallel. It is used by writable external tables to accept output streams from Greenplum Database segments in parallel and write them out to a file.

In order for <code>gpfdist</code> to be used by an external table, the <code>LOCATION</code> clause of the external table definition must specify the correct file location using the <code>gpfdist://protocol</code> (see <code>CREATE EXTERNAL TABLE</code>).

The benefit of using gpfdist is that you are guaranteed maximum parallelism while reading from or writing to external tables, thereby offering the best performance as well as easier administration of external tables.

For readable external tables, <code>gpfdist</code> parses and serves data files evenly to all the segment instances in the Greenplum Database system when users <code>SELECT</code> from the external table. For writable external tables, <code>gpfdist</code> accepts parallel output streams from the segments when users <code>INSERT</code> into the external table, and writes to an output file.

For readable external tables, if load files are compressed using gzip or bzip2 (have a .gz or .bz2 file extension), gpfdist will uncompress the files automatically before loading provided that gunzip or bunzip2 is in your path. Writable external tables do not currently support compression.

Most likely, you will want to run gpfdist on your ETL machines rather than the hosts where Greenplum Database is installed. To install gpfdist on another host, simply copy the utility over to that host and add gpfdist to your \$PATH.

Options

-d directory

The directory from which gpfdist will serve files for readable external tables or create output files for writable external tables. If not specified, defaults to the current directory.

-l log file

The fully qualified path and log file name where standard output messages are to be logged.

-p http port

The HTTP port on which gpfdist will serve files. Defaults to 8080.

-t timeout

Sets the time allowed for Greenplum Database to establish a connection to a gpfdist process. Default is 5 seconds. Allowed values are 2 to 30 seconds. May need to be increased on systems with a lot of network traffic.

-m *max* length

Sets the maximum allowed data row length in bytes. Default is 32768. Should be used when user data includes very wide rows (or when line too long error message occurs). Should not be used otherwise as it increases resource allocation. Valid range is 32K to 1MB.

-? (help)

Displays the online help.

-v (verbose)

Verbose mode shows progress and status messages.

-V (very verbose)

Verbose mode shows all output messages generated by this utility.

--version

Displays the version of this utility.

Examples

Serve files from a specified directory using port 8081 (and start gpfdist in the background):

```
gpfdist -d /var/load files -p 8081 &
```

Start gpfdist in the background and redirect output and errors to a log file:

```
gpfdist -d /var/load files -p 8081 -l /home/gpadmin/log &
```

To stop gpfdist when it is running in the background:

--First find its process id:

```
ps ax | grep gpfdist
```

OR on Solaris

```
ps -ef | grep gpfdist
```

-- Then kill the process, for example:

```
kill 3456
```

See Also

CREATE EXTERNAL TABLE, gpload

gpload

Runs a load job as defined in a YAML formatted control file.

Synopsis

```
gpload -f control_file [-l log_file] [-h hostname] [-p port] [-U
username] [-d database] [-W] [--gpfdist_timeout seconds] [[-v |
-V] [-q]] [-D]
gpload -?
gpload --version
```

Prerequisites

The client machine where gpload is executed must have the following:

- Python 2.6.2 or later, pygresql (the Python interface to PostgreSQL), and pyyaml. Note that Python and the required Python libraries are included with the Greenplum Database server installation, so if you have Greenplum Database installed on the machine where gpload is running, you do not need a separate Python installation.
- The gpfdist parallel file distribution program installed and in your \$PATH. This program is located in \$GPHOME/bin of your Greenplum Database server installation.
- Network access to and from all hosts in your Greenplum Database array (master and segments).
- Network access to and from the hosts where the data to be loaded resides (ETL servers).

Description

gpload is a data loading utility that acts as an interface to Greenplum Database's external table parallel loading feature. Using a load specification defined in a YAML formatted control file, gpload executes a load by invoking the Greenplum parallel file server (gpfdist), creating an external table definition based on the source data defined, and executing an INSERT, UPDATE or MERGE operation to load the source data into the target table in the database.

Options

-f control file

Required. A YAML file that contains the load specification details. See "Control File Format" on page 10.

--gpfdist timeout seconds

Sets the timeout for the <code>gpfdist</code> parallel file distribution program to send a response. Enter a value from 0 to 30 seconds (entering "0" to disables timeouts). Note that you might need to increase this value when operating on high-traffic networks.

-1 log file

Specifies where to write the log file. Defaults to ~/gpAdminLogs/gpload YYYYMMDD. See also, "Log File Format" on page 17.

-v (verbose mode)

Show verbose output of the load steps as they are executed.

-V (very verbose mode)

Shows very verbose output.

-q (no screen output)

Run in quiet mode. Command output is not displayed on the screen, but is still written to the log file.

-D (debug mode)

Check for error conditions, but do not execute the load.

-? (show help)

Show help, then exit.

--version

Show the version of this utility, then exit.

Connection Options

-d database

The database to load into. If not specified, reads from the load control file, the environment variable \$PGDATABASE or defaults to the current system user name.

-h hostname

Specifies the host name of the machine on which the Greenplum master database server is running. If not specified, reads from the load control file, the environment variable \$PGHOST or defaults to localhost.

-p port

Specifies the TCP port on which the Greenplum master database server is listening for connections. If not specified, reads from the load control file, the environment variable SPGPORT or defaults to 5432

-U username

The database role name to connect as. If not specified, reads from the load control file, the environment variable \$PGUSER or defaults to the current system user name.

-W (force password prompt)

Force a password prompt. If not specified, reads the password from the environment variable \$PGPASSWORD or from a password file specified by \$PGPASSFILE or in ~/.pgpass. If these are not set, then gpload will prompt for a password even if -W is not supplied.

Control File Format

The gpload control file uses the YAML 1.1 document format and then implements its own schema for defining the various steps of a Greenplum Database load operation. The control file must be a valid YAML document.

The gpload program processes the control file document in order and uses indentation (spaces) to determine the document hierarchy and the relationships of the sections to one another. The use of white space is significant. White space should not be used simply for formatting purposes, and tabs should not be used at all.

The basic structure of a load control file is:

```
VERSION: 1.0.0.1
DATABASE: db name
USER: db username
HOST: master hostname
PORT: master port
GPLOAD:
  INPUT:
   - SOURCE:
        LOCAL HOSTNAME:
          - hostname_or_ip
        PORT: http port
       | PORT RANGE: [start port range, end port range]
        FILE:
           - /path/to/input file
    - COLUMNS:
           - field name: data type
    - FORMAT: text | csv
    - DELIMITER: 'delimiter character'
    - ESCAPE: 'escape character' | 'OFF'
    - NULL AS: 'null string'
    - FORCE NOT NULL: true | false
    - QUOTE: 'csv quote character'
    - HEADER: true | false
    - ENCODING: database encoding
```

```
- ERROR LIMIT: integer
- ERROR TABLE: schema.table name
OUTPUT:
- TABLE: schema.table name
- MODE: insert | update | merge
- MATCH COLUMNS:
       - target column name
 - UPDATE COLUMNS:
       - target column name
- UPDATE CONDITION: 'boolean condition'
- MAPPING:
         target column name: source column name | 'expression'
PRELOAD:
- TRUNCATE: true | false
- REUSE TABLES: true | false
SOL:
- BEFORE: "sql command"
- AFTER: "sql command"
```

VERSION

Optional. The version of the gpload control file schema. The current version is 1.0.0.1.

DATABASE

Optional. Specifies which database in Greenplum to connect to. If not specified, defaults to \$PGDATABASE if set or the current system user name. You can also specify the database on the command line using the -d option.

USER

Optional. Specifies which database role to use to connect. If not specified, defaults to the current user or \$PGUSER if set. You can also specify the database role on the command line using the -U option.

If the user running <code>gpload</code> is not a Greenplum superuser, then the server configuration parameter <code>gp_external_grant_privileges</code> must be set to on in order for the load to be processed.

HOST

Optional. Specifies Greenplum master host name. If not specified, defaults to localhost or \$PGHOST if set. You can also specify the master host name on the command line using the -h option.

PORT

Optional. Specifies Greenplum master port. If not specified, defaults to 5432 or \$PGPORT if set. You can also specify the master port on the command line using the -p option.

GPLOAD

Required. Begins the load specification section. A GPLOAD specification must have an INPUT and an OUTPUT section defined.

INPUT

Required. Defines the location and the format of the input data to be loaded. gpload will start one or more instances of the gpfdist file distribution program on the current host and create the required external table definition(s) in Greenplum Database that point to the source data. Note that the host from which you run gpload must be accessible over the network by all Greenplum hosts (master and segments).

SOURCE

Required. The SOURCE block of an INPUT specification defines the location of a source file. An INPUT section can have more than one SOURCE block defined. Each SOURCE block defined corresponds to one instance of the gpfdist file distribution program that will be started on the local machine. Each SOURCE block defined must have a FILE specification.

LOCAL HOSTNAME

Optional. Specifies the host name or IP address of the local machine on which <code>gpload</code> is running. If this machine is configured with multiple network interface cards (NICs), you can specify the host name or IP of each individual NIC to allow network traffic to use all NICs simultaneously. The default is to use the local machine's primary host name or IP only.

PORT

Optional. Specifies the specific port number that the <code>gpfdist</code> file distribution program should use. You can also supply a <code>PORT_RANGE</code> to select an available port from the specified range. If both <code>PORT</code> and <code>PORT_RANGE</code> are defined, then <code>PORT</code> takes precedence. If neither <code>PORT</code> or <code>PORT_RANGE</code> are defined, the default is to select an available port between 8000 and 9000.

If multiple host names are declared in LOCAL_HOSTNAME, this port number is used for all hosts. This configuration is desired if you want to use all NICs to load the same file or set of files in a given directory location.

PORT RANGE

Optional. Can be used instead of PORT to supply a range of port numbers from which gpload can choose an available port for this instance of the gpfdist file distribution program.

FILE

Required. Specifies the location of a file, named pipe, or directory location on the local file system that contains data to be loaded. You can declare more than one file so long as the data is of the same format in all files specified.

If the files are compressed using gzip or bzip2 (have a .gz or .bz2 file extension), the files will be uncompressed automatically (provided that gunzip or bunzip2 is in your path).

When specifying which source files to load, you can use the wildcard character (*) or other C-style pattern matching to denote multiple files. The files specified are assumed to be relative to the current directory from which gpload is executed (or you can declare an absolute path).

COLUMNS

Optional. Specifies the schema of the source data file(s) in the format of $field_name$: $data_type$. The DELIMITER character in the source file is what separates two data value fields (columns). A row is determined by a line feed character (0x0a).

If the input COLUMNS are not specified, then the schema of the output TABLE is implied, meaning that the source data must have the same column order, number of columns, and data format as the target table.

The default source-to-target mapping is based on a match of column names as defined in this section and the column names in the target TABLE. This default mapping can be overridden using the MAPPING section.

FORMAT

Optional. Specifies the format of the source data file(s) - either plain text (TEXT) or comma separated values (CSV) format. Defaults to TEXT if not specified.

DELIMITER

Optional. Specifies a single ASCII character that separates columns within each row (line) of data. The default is a tab character in TEXT mode, a comma in CSV mode. You can also specify a non-printable ASCII character via an escape sequence using the decimal representation of the ASCII character. For example, \014 represents the shift out character.

ESCAPE

Specifies the single character that is used for C escape sequences (such as $\n,\t,\100$, and so on) and for escaping data characters that might otherwise be taken as row or column delimiters. Make sure to choose an escape character that is not used anywhere in your actual column data. The default escape character is a \ (backslash) for text-formatted files and a " (double quote) for csv-formatted files, however it is possible to specify another character to represent an escape. It is also possible to disable escaping in

text-formatted files by specifying the value 'OFF' as the escape value. This is very useful for data such as text-formatted web log data that has many embedded backslashes that are not intended to be escapes.

NULL AS

Optional. Specifies the string that represents a null value. The default is \N (backslash-N) in TEXT mode, and an empty value with no quotations in CSV mode. You might prefer an empty string even in TEXT mode for cases where you do not want to distinguish nulls from empty strings. Any source data item that matches this string will be considered a null value.

FORCE_NOT_NULL

Optional. In CSV mode, processes each specified column as though it were quoted and hence not a NULL value. For the default null string in CSV mode (nothing between two delimiters), this causes missing values to be evaluated as zero-length strings.

QUOTE

Required when FORMAT is CSV. Specifies the quotation character for CSV mode. The default is double-quote (").

HEADER

Optional. Specifies that the first line in the data file(s) is a header row (contains the names of the columns) and should not be included as data to be loaded. If using multiple data source files, all files must have a header row. The default is to assume that the input files do not have a header row.

ENCODING

Optional. Character set encoding of the source data. Specify a string constant (such as 'SQL_ASCII'), an integer encoding number, or 'DEFAULT' to use the default client encoding. If not specified, the default client encoding is used.

ERROR LIMIT

Optional. Enables single row error isolation mode for this load operation. When enabled, input rows that have format errors will be discarded provided that the error limit count is not reached on any Greenplum segment instance during input processing. If the error limit is not reached, all good rows will be loaded and any error rows will either be discarded or logged to the table specified in ERROR_TABLE. The default is to abort the load operation on the first error encountered. Note that single row error isolation only applies to data rows with format errors; for example, extra or missing attributes, attributes of a wrong data type, or invalid client encoding sequences. Constraint errors, such as primary key violations, will still cause the load operation to abort if encountered.

ERROR TABLE

Optional when ERROR_LIMIT is declared. Specifies an error table where rows with formatting errors will be logged when running in single row error isolation mode. You can then examine this error table to see error rows that were not loaded (if any). If the <code>error_table</code> specified already exists, it will be used. If it does not exist, it will be automatically generated.

OUTPUT

Required. Defines the target table and final data column values that are to be loaded into the database

TABLE

Required. The name of the target table to load into.

MODE

Optional. Defaults to INSERT if not specified. There are three available load modes:

INSERT - Loads data into the target table using the following method:
INSERT INTO target table SELECT * FROM input data;

UPDATE - Updates the <code>UPDATE_COLUMNS</code> of the target table where the rows have <code>MATCH_COLUMNS</code> attribute values equal to those of the input data, and the optional <code>UPDATE_CONDITION</code> is true. <code>UPDATE</code> is not supported on tables with a random distribution policy.

MERGE - Inserts new rows and updates the UPDATE_COLUMNS of existing rows where MATCH_COLUMNS attribute values are equal to those of the input data, and the optional UPDATE_CONDITION is true. New rows are identified when the MATCH_COLUMNS value in the source data does not have a corresponding value in the existing data of the target table. If there are multiple new MATCH_COLUMNS values that are the same, only one new row for that value will be inserted (use UPDATE_CONDITION to filter out the rows you want to discard). MERGE is not supported on tables with a random distribution policy.

MATCH COLUMNS

Required if MODE is UPDATE or MERGE. Specifies the column(s) to use as the join condition for the update. The attribute value in the specified target column(s) must be equal to that of the corresponding source data column(s) in order for the row to be updated in the target table.

UPDATE COLUMNS

Required if MODE is UPDATE or MERGE. Specifies the column(s) to update for the rows that meet the MATCH_COLUMNS criteria and the optional UPDATE_CONDITION. Update columns cannot be columns that are used for the Greenplum distribution key for the table.

UPDATE CONDITION

Optional. Specifies a Boolean condition (similar to what you would declare in a WHERE clause) that must be met in order for a row in the target table to be updated (or inserted in the case of a MERGE).

MAPPING

Optional. If a mapping is specified, it overrides the default source-to-target column mapping. The default source-to-target mapping is based on a match of column names as defined in the source COLUMNS section and the column names of the target TABLE. A mapping is specified as either:

```
target_column_name: source_column_name
or
  target column name: 'expression'
```

Where *expression* is any expression that you would specify in the SELECT list of a query, such as a constant value, a column reference, an operator invocation, a function call, and so on.

PRELOAD

Optional. Specifies operations to run prior to the load operation. Right now the only preload operation is TRUNCATE.

TRUNCATE

Optional. If set to true, gpload will remove all rows in the target table prior to loading it.

REUSE TABLES

Optional. If set to true, gpload will not drop the external table objects and staging table objects it creates. These objects will be reused for future load operations that use the same load specifications. This improves performance of trickle loads (ongoing small loads to the same target table).

SOL

Optional. Defines SQL commands to run before and/or after the load operation. You can specify multiple BEFORE and/or AFTER commands. List commands in the order of desired execution.

BEFORE

Optional. An SQL command to run before the load operation starts. Enclose commands in quotes.

AFTER

Optional. An SQL command to run after the load operation completes. Enclose commands in quotes.

Notes

If your database object names were created using a double-quoted identifier (delimited identifier), you must specify the delimited name within single quotes in the gpload control file. For example, if you create a table as follows:

```
CREATE TABLE "MyTable" ("MyColumn" text);
```

Your YAML-formatted gpload control file would refer to the above table and column names as follows:

```
- COLUMNS:
    - '"MyColumn"': text
OUTPUT:
    - TABLE: public.'"MyTable"'
```

Log File Format

Log files output by gpload have the following format:

```
timestamp|level|message
```

Where timestamp takes the form: YYYY-MM-DD HH:MM:SS, level is one of DEBUG, LOG, INFO, ERROR, and message is a normal text message.

Some INFO messages that may be of interest in the log files are (where # corresponds to the actual number of seconds, units of data, or failed rows):

```
INFO|running time: #.## seconds
INFO|transferred #.# kB of #.# kB.
INFO|gpload succeeded
INFO|gpload succeeded with warnings
INFO|gpload failed
INFO|1 bad row
INFO|# bad rows
```

Examples

Run a load job as defined in my load.yml:

```
gpload -f my_load.yml
```

Example load control file:

```
VERSION: 1.0.0.1

DATABASE: ops

USER: gpadmin

HOST: mdw-1

PORT: 5432

GPLOAD:

INPUT:

- SOURCE:

LOCAL_HOSTNAME:

- etll-1
```

```
- etl1-2
        - etl1-3
        - etl1-4
      PORT: 8081
      FILE:
       - /var/load/data/*
 - COLUMNS:
        - name: text
        - amount: float4
        - category: text
        - desc: text
        - date: date
 - FORMAT: text
 - DELIMITER: '|'
 - ERROR LIMIT: 25
 - ERROR_TABLE: payables.err_expenses
 - TABLE: payables.expenses
- MODE: INSERT
SQL:
- BEFORE: "INSERT INTO audit VALUES('start', current_timestamp)"
- AFTER: "INSERT INTO audit VALUES('end', current_timestamp)"
```

See Also

gpfdist, CREATE EXTERNAL TABLE

B. SQL Command Reference

This is a summary of the SQL command syntax supported in Greenplum Database 4.1. For the full SQL command usage and descriptions, see the *Greenplum Database Administrator Guide*.

SQL Syntax Summary

ABORT

Aborts the current transaction.

```
ABORT [WORK | TRANSACTION]
```

ALTER AGGREGATE

Changes the definition of an aggregate function

```
ALTER AGGREGATE name ( type [ , ... ] ) RENAME TO new_name

ALTER AGGREGATE name ( type [ , ... ] ) OWNER TO new_owner

ALTER AGGREGATE name ( type [ , ... ] ) SET SCHEMA new schema
```

ALTER CONVERSION

Changes the definition of a conversion.

```
ALTER CONVERSION name RENAME TO newname
ALTER CONVERSION name OWNER TO newowner
```

ALTER DATABASE

Changes the attributes of a database.

```
ALTER DATABASE name [ WITH CONNECTION LIMIT connlimit ]

ALTER DATABASE name SET parameter { TO | = } { value | DEFAULT }

ALTER DATABASE name RESET parameter

ALTER DATABASE name RENAME TO newname

ALTER DATABASE name OWNER TO new owner
```

ALTER DOMAIN

Changes the definition of a domain.

```
ALTER DOMAIN name { SET DEFAULT expression | DROP DEFAULT }
ALTER DOMAIN name { SET | DROP } NOT NULL
ALTER DOMAIN name ADD domain_constraint
ALTER DOMAIN name DROP CONSTRAINT constraint_name [RESTRICT | CASCADE]
ALTER DOMAIN name OWNER TO new_owner
ALTER DOMAIN name SET SCHEMA new schema
```

SQL Syntax Summary

ALTER EXTERNAL TABLE

Changes the definition of an external table.

```
ALTER EXTERNAL TABLE name RENAME [COLUMN] column TO new_column
ALTER EXTERNAL TABLE name RENAME TO new_name
ALTER EXTERNAL TABLE name SET SCHEMA new_schema
ALTER EXTERNAL TABLE name action [, ...]
where action is one of:
ADD [COLUMN] column_name type
DROP [COLUMN] column
ALTER [COLUMN] column
OWNER TO new_owner
```

ALTER FILESPACE

Changes the definition of a filespace.

```
ALTER FILESPACE name RENAME TO newname ALTER FILESPACE name OWNER TO newowner
```

ALTER FUNCTION

Changes the definition of a function.

```
ALTER FUNCTION name ( [ [argmode] [argname] argtype [, ...] ] ) action [, ...] [RESTRICT]

ALTER FUNCTION name ( [ [argmode] [argname] argtype [, ...] ] ) RENAME TO new_name ALTER FUNCTION name ( [ [argmode] [argname] argtype [, ...] ] ) OWNER TO new_owner ALTER FUNCTION name ( [ [argmode] [argname] argtype [, ...] ] ) SET SCHEMA new schema
```

where *action* is one of:

```
{CALLED ON NULL INPUT | RETURNS NULL ON NULL INPUT | STRICT} {IMMUTABLE | STABLE | VOLATILE} {[EXTERNAL] SECURITY INVOKER | [EXTERNAL] SECURITY DEFINER}
```

ALTER GROUP

Changes a role name or membership.

```
ALTER GROUP groupname ADD USER username [, ...]

ALTER GROUP groupname DROP USER username [, ...]

ALTER GROUP groupname RENAME TO newname
```

ALTER INDEX

Changes the definition of an index.

```
ALTER INDEX name RENAME TO new_name

ALTER INDEX name SET TABLESPACE tablespace_name

ALTER INDEX name SET ( FILLFACTOR = value )

ALTER INDEX name RESET ( FILLFACTOR )
```

ALTER LANGUAGE

Changes the name of a procedural language.

```
ALTER LANGUAGE name RENAME TO newname
```

ALTER OPERATOR

Changes the definition of an operator.

```
ALTER OPERATOR name ( {lefttype | NONE} , {righttype | NONE} ) OWNER TO newowner
```

ALTER OPERATOR CLASS

Changes the definition of an operator class.

```
ALTER OPERATOR CLASS name USING index_method RENAME TO newname ALTER OPERATOR CLASS name USING index method OWNER TO newowner
```

ALTER RESOURCE QUEUE

Changes the limits of a resource queue.

```
ALTER RESOURCE QUEUE name WITH ( queue_attribute=value [, ...] )

where queue_attribute is:
    ACTIVE_STATEMENTS=integer
    MEMORY_LIMIT='memory_units'
    MAX_COST=float
    COST_OVERCOMMIT={TRUE|FALSE}
    MIN_COST=float
    PRIORITY={MIN|LOW|MEDIUM|HIGH|MAX}

ALTER RESOURCE QUEUE name WITHOUT ( queue_attribute=value [, ...] )

where queue_attribute is:
    ACTIVE_STATEMENTS=integer
    MEMORY_LIMIT='memory_units'
    MAX_COST=float
    COST_OVERCOMMIT={TRUE|FALSE}
    MIN_COST=float
```

ALTER ROLE

Changes a database role (user or group).

ALTER ROLE name RENAME TO newname

```
ALTER ROLE name SET config parameter {TO | =} {value | DEFAULT}
ALTER ROLE name RESET config parameter
ALTER ROLE name RESOURCE QUEUE {queue name | NONE}
ALTER ROLE name [ [WITH] option [ ... ] ]
where option can be:
     SUPERUSER | NOSUPERUSER
    | CREATEDB | NOCREATEDB
    | CREATEROLE | NOCREATEROLE
    | CREATEEXTTABLE | NOCREATEEXTTABLE
      [ ( attribute='value'[, ...] ) ]
           where attributes and values are:
          type='readable'|'writable'
          protocol='gpfdist'|'http'|'gphdfs'
| INHERIT | NOINHERIT
   | LOGIN | NOLOGIN
    | CONNECTION LIMIT connlimit
    | [ENCRYPTED | UNENCRYPTED] PASSWORD 'password'
    | VALID UNTIL 'timestamp'
```

SQL Syntax Summary

ALTER SCHEMA

Changes the definition of a schema.

```
ALTER SCHEMA name RENAME TO newname ALTER SCHEMA name OWNER TO newowner
```

ALTER SEQUENCE

Changes the definition of a sequence generator.

```
ALTER SEQUENCE name [INCREMENT [ BY ] increment]

[MINVALUE minvalue | NO MINVALUE]

[MAXVALUE maxvalue | NO MAXVALUE]

[RESTART [ WITH ] start]

[CACHE cache] [[ NO ] CYCLE]

[OWNED BY {table.column | NONE}]

ALTER SEQUENCE name SET SCHEMA new schema
```

ALTER TABLE

Changes the definition of a table.

```
ALTER TABLE [ONLY] name RENAME [COLUMN] column TO new_column

ALTER TABLE name RENAME TO new_name

ALTER TABLE name SET SCHEMA new_schema

ALTER TABLE [ONLY] name SET

DISTRIBUTED BY (column, [ ... ] )
| DISTRIBUTED RANDOMLY
| WITH (REORGANIZE=true|false)

ALTER TABLE [ONLY] name action [, ... ]

ALTER TABLE name
[ ALTER PARTITION { partition name | FOR (RANK(number)) | FOR (value) }
```

SQL Syntax Summary

```
partition action [...] ]
   partition action
where action is one of:
 ADD [COLUMN] column name type [column constraint [ ... ]]
 DROP [COLUMN] column [RESTRICT | CASCADE]
 ALTER [COLUMN] column TYPE type [USING expression]
 ALTER [COLUMN] column SET DEFAULT expression
 ALTER [COLUMN] column DROP DEFAULT
 ALTER [COLUMN] column { SET | DROP } NOT NULL
 ALTER [COLUMN] column SET STATISTICS integer
 ADD table constraint
 DROP CONSTRAINT constraint name [RESTRICT | CASCADE]
 DISABLE TRIGGER [trigger name | ALL | USER]
 ENABLE TRIGGER [trigger name | ALL | USER]
 CLUSTER ON index name
 SET WITHOUT CLUSTER
 SET WITHOUT OIDS
 SET (FILLFACTOR = value)
 RESET (FILLFACTOR)
 INHERIT parent table
 NO INHERIT parent table
 OWNER TO new owner
 SET TABLESPACE new tablespace
 ALTER DEFAULT PARTITION
 DROP DEFAULT PARTITION [IF EXISTS]
 DROP PARTITION [IF EXISTS] { partition name |
     FOR (RANK(number)) | FOR (value) } [CASCADE]
 TRUNCATE DEFAULT PARTITION
  TRUNCATE PARTITION { partition name | FOR (RANK(number)) |
     FOR (value) }
 RENAME DEFAULT PARTITION TO new partition name
 RENAME PARTITION { partition name | FOR (RANK(number)) |
     FOR (value) } TO new partition name
 ADD DEFAULT PARTITION name [ ( subpartition spec ) ]
 ADD PARTITION [name] partition element
     [ ( subpartition spec ) ]
  EXCHANGE PARTITION { partition name | FOR (RANK(number)) |
      FOR (value) } WITH TABLE table name
       [ WITH | WITHOUT VALIDATION ]
 EXCHANGE DEFAULT PARTITION WITH TABLE table name
  [ WITH | WITHOUT VALIDATION ]
 SET SUBPARTITION TEMPLATE (subpartition spec)
 SPLIT DEFAULT PARTITION
    { AT (list value)
     | START([datatype] range value) [INCLUSIVE | EXCLUSIVE]
       END([datatype] range_value) [INCLUSIVE | EXCLUSIVE] }
    [ INTO ( PARTITION new partition name,
            PARTITION default partition name ) ]
 SPLIT PARTITION { partition name | FOR (RANK(number)) |
    FOR (value) } AT (value)
    [ INTO (PARTITION partition name, PARTITION partition name)]
where partition element is:
   VALUES (list value [,...])
  | START ([datatype] 'start value') [INCLUSIVE | EXCLUSIVE]
     [ END ([datatype] 'end value') [INCLUSIVE | EXCLUSIVE] ]
```

```
| END ([datatype] 'end value') [INCLUSIVE | EXCLUSIVE]
[ WITH ( partition storage parameter=value [, ... ] ) ]
[ TABLESPACE tablespace ]
where subpartition spec is:
subpartition element [, ...]
and subpartition element is:
  DEFAULT SUBPARTITION name
  | [SUBPARTITION name] VALUES (list value [,...] )
  | [SUBPARTITION name]
    START ([datatype] 'start_value') [INCLUSIVE | EXCLUSIVE]
    [ END ([datatype] 'end value') [INCLUSIVE | EXCLUSIVE] ]
    [ EVERY ( [number | datatype] 'interval value') ]
  | [SUBPARTITION name]
    END ([datatype] 'end value') [INCLUSIVE | EXCLUSIVE]
    [ EVERY ( [number | datatype] 'interval value') ]
[ WITH ( partition storage parameter=value [, ... ] ) ]
[ TABLESPACE tablespace ]
where storage parameter is:
  APPENDONLY={TRUE | FALSE}
  COMPRESSTYPE={ZLIB|QUICKLZ}
  COMPRESSLEVEL={0-9|1}
  ORIENTATION={COLUMN | ROW}
  FILLFACTOR={10-100}
```

ALTER TABLESPACE

Changes the definition of a tablespace.

```
ALTER TABLESPACE name RENAME TO newname
ALTER TABLESPACE name OWNER TO newowner
```

ALTER TRIGGER

Changes the definition of a trigger.

```
ALTER TRIGGER name ON table RENAME TO newname
```

ALTER TYPE

Changes the definition of a data type.

```
ALTER TYPE name OWNER TO new_owner
ALTER TYPE name SET SCHEMA new schema
```

ALTER USER

Changes the definition of a database role (user).

```
ALTER USER name RENAME TO newname

ALTER USER name SET config_parameter {TO | =} {value | DEFAULT}

ALTER USER name RESET config_parameter

ALTER USER name [ [WITH] option [ ... ] ]

where option can be:

SUPERUSER | NOSUPERUSER

| CREATEDB | NOCREATEDB

| CREATEROLE | NOCREATEROLE

| CREATEUSER | NOCREATEUSER

| INHERIT | NOINHERIT

| LOGIN | NOLOGIN

| [ ENCRYPTED | UNENCRYPTED ] PASSWORD 'password'

| VALID UNTIL 'timestamp'
```

ANALYZE

Collects statistics about a database.

```
ANALYZE [VERBOSE] [table [ (column [, ...] ) ]]
```

BEGIN

Starts a transaction block.

```
BEGIN [WORK | TRANSACTION] [SERIALIZABLE | REPEATABLE READ | READ COMMITTED | READ UNCOMMITTED] [READ WRITE | READ ONLY]
```

CHECKPOINT

Forces a transaction log checkpoint.

CHECKPOINT

CLOSE

Closes a cursor.

```
CLOSE cursor name
```

CLUSTER

Physically reorders a heap storage table on disk according to an index. Not a recommended operation in Greenplum Database.

```
CLUSTER indexname ON tablename
CLUSTER tablename
CLUSTER
```

COMMENT

Defines or change the comment of an object.

```
COMMENT ON
{ TABLE object name |
 COLUMN table name.column name |
 AGGREGATE agg_name (agg_type [, ...]) |
 CAST (sourcetype AS targettype) |
 CONSTRAINT constraint_name ON table_name |
 CONVERSION object name |
 DATABASE object name |
 DOMAIN object name |
 FILESPACE object name |
 FUNCTION func name ([[argmode] [argname] argtype [, ...]]) |
 INDEX object name |
 LARGE OBJECT large object oid |
 OPERATOR op (leftoperand type, rightoperand type) |
 OPERATOR CLASS object_name USING index_method |
 [PROCEDURAL] LANGUAGE object name |
 RESOURCE QUEUE object name |
 ROLE object name |
 RULE rule name ON table name |
 SCHEMA object name |
 SEQUENCE object name |
 TABLESPACE object name |
 TRIGGER trigger name ON table name |
 TYPE object_name |
 VIEW object name }
IS 'text'
```

COMMIT

Commits the current transaction.

```
COMMIT [WORK | TRANSACTION]
```

COPY

Copies data between a file and a table.

```
COPY table [(column [, ...])] FROM {'file' | STDIN}
     [ [WITH]
       [OIDS]
       [HEADER]
       [DELIMITER [ AS ] 'delimiter']
       [NULL [ AS ] 'null string']
       [ESCAPE [ AS ] 'escape' | 'OFF']
       [NEWLINE [ AS ] 'LF' | 'CR' | 'CRLF']
       [CSV [QUOTE [ AS ] 'quote']
            [FORCE NOT NULL column [, ...]]
       [FILL MISSING FIELDS]
     [ [LOG ERRORS INTO error table] [KEEP]
       SEGMENT REJECT LIMIT count [ROWS | PERCENT] ]
COPY {table [(column [, ...])] | (query)} TO {'file' | STDOUT}
      [ [WITH]
        [OIDS]
        [HEADER]
        [DELIMITER [ AS ] 'delimiter']
        [NULL [ AS ] 'null string']
        [ESCAPE [ AS ] 'escape' | 'OFF']
        [CSV [QUOTE [ AS ] 'quote']
             [FORCE QUOTE column [, ...]] ]
```

CREATE AGGREGATE

Defines a new aggregate function.

```
CREATE AGGREGATE name (input_data_type [ , ... ])

( SFUNC = sfunc,
    STYPE = state_data_type
    [, PREFUNC = prefunc]
    [, FINALFUNC = ffunc]
    [, INITCOND = initial_condition]
    [, SORTOP = sort_operator] )
```

CREATE CAST

Defines a new cast.

```
CREATE CAST (sourcetype AS targettype)
WITH FUNCTION funcname (argtypes)
[AS ASSIGNMENT | AS IMPLICIT]

CREATE CAST (sourcetype AS targettype) WITHOUT FUNCTION
[AS ASSIGNMENT | AS IMPLICIT]
```

CREATE CONVERSION

Defines a new encoding conversion.

CREATE [DEFAULT] CONVERSION name FOR source encoding TO dest encoding FROM funcname

CREATE DATABASE

Creates a new database.

CREATE DOMAIN

Defines a new domain.

CREATE EXTERNAL TABLE

Defines a new external table.

```
CREATE [READABLE] EXTERNAL TABLE table name
     ( column name data type [, ...] | LIKE other table )
     LOCATION ('file://seghost[:port]/path/file' [, ...])
          | ('gpfdist://filehost[:port]/file pattern' [, ...])
          ('gphdfs://hdfs host[:port]/path/file')
      FORMAT 'TEXT'
           [( [HEADER]
               [DELIMITER [AS] 'delimiter' | 'OFF']
               [NULL [AS] 'null string']
               [ESCAPE [AS] 'escape' | 'OFF']
               [NEWLINE [ AS ] 'LF' | 'CR' | 'CRLF']
               [FILL MISSING FIELDS] )]
           | 'CSV'
            [( [HEADER]
               [QUOTE [AS] 'quote']
               [DELIMITER [AS] 'delimiter']
               [NULL [AS] 'null string']
               [FORCE NOT NULL column [, ...]]
               [ESCAPE [AS] 'escape']
               [NEWLINE [ AS ] 'LF' | 'CR' | 'CRLF']
              [FILL MISSING FIELDS] )]
     [ ENCODING 'encoding' ]
     [ [LOG ERRORS INTO error table] SEGMENT REJECT LIMIT count
       [ROWS | PERCENT] ]
CREATE [READABLE] EXTERNAL WEB TABLE table name
     ( column name data type [, ...] | LIKE other table )
     LOCATION ('http://webhost[:port]/path/file' [, ...])
    | EXECUTE 'command' [ON ALL
                          | MASTER
                          | number of segments
                          | HOST ['segment hostname']
                          | SEGMENT segment id ]
     FORMAT 'TEXT'
           [( [HEADER]
              [DELIMITER [AS] 'delimiter' | 'OFF']
               [NULL [AS] 'null string']
               [ESCAPE [AS] 'escape' | 'OFF']
               [NEWLINE [ AS ] 'LF' | 'CR' | 'CRLF']
               [FILL MISSING FIELDS] )]
           I 'CSV'
            [( [HEADER]
               [QUOTE [AS] 'quote']
               [DELIMITER [AS] 'delimiter']
               [NULL [AS] 'null string']
               [FORCE NOT NULL column [, ...]]
               [ESCAPE [AS] 'escape']
               [NEWLINE [ AS ] 'LF' | 'CR' | 'CRLF']
               [FILL MISSING FIELDS] )]
     [ ENCODING 'encoding' ]
     [ [LOG ERRORS INTO error table] SEGMENT REJECT LIMIT count
       [ROWS | PERCENT] ]
CREATE WRITABLE EXTERNAL TABLE table name
    ( column name data type [, ...] | LIKE other table )
      LOCATION ('gpfdist://outputhost[:port]/filename' [, ...])
```

```
('gphdfs://hdfs host[:port]/path')
     FORMAT 'TEXT'
               [( [DELIMITER [AS] 'delimiter']
               [NULL [AS] 'null string']
               [ESCAPE [AS] 'escape' | 'OFF'] )]
          | 'CSV'
              [([QUOTE [AS] 'quote']
              [DELIMITER [AS] 'delimiter']
               [NULL [AS] 'null string']
               [FORCE QUOTE column [, ...]]]
               [ESCAPE [AS] 'escape'] )]
    [ ENCODING 'write encoding' ]
    [ DISTRIBUTED BY (column, [ ... ] ) | DISTRIBUTED RANDOMLY ]
CREATE WRITABLE EXTERNAL WEB TABLE table name
    ( column name data type [, ...] | LIKE other table )
    EXECUTE 'command' [ON ALL]
    FORMAT 'TEXT'
               [( [DELIMITER [AS] 'delimiter']
               [NULL [AS] 'null string']
              [ESCAPE [AS] 'escape' | 'OFF'] )]
          | 'CSV'
              [([QUOTE [AS] 'quote']
               [DELIMITER [AS] 'delimiter']
               [NULL [AS] 'null string']
               [FORCE QUOTE column [, ...]]]
               [ESCAPE [AS] 'escape'] )]
    [ ENCODING 'write encoding' ]
    [ DISTRIBUTED BY (column, [ ... ] ) | DISTRIBUTED RANDOMLY ]
CREATE FUNCTION
Defines a new function.
CREATE [OR REPLACE] FUNCTION name
```

```
([[argmode] [argname] argtype [, ...]])
[RETURNS [SETOF] rettype]
{ LANGUAGE languame
| IMMUTABLE | STABLE | VOLATILE
| CALLED ON NULL INPUT | RETURNS NULL ON NULL INPUT | STRICT
| [EXTERNAL] SECURITY INVOKER | [EXTERNAL] SECURITY DEFINER
| AS 'definition'
| AS 'obj file', 'link symbol' } ...
```

CREATE GROUP

Defines a new database role.

```
CREATE GROUP name [ [WITH] option [ ... ] ]
where option can be:
     SUPERUSER | NOSUPERUSER
    | CREATEDB | NOCREATEDB
    | CREATEROLE | NOCREATEROLE
    | CREATEUSER | NOCREATEUSER
    | INHERIT | NOINHERIT
    | LOGIN | NOLOGIN
    | [ ENCRYPTED | UNENCRYPTED ] PASSWORD 'password'
    | VALID UNTIL 'timestamp'
    | IN ROLE rolename [, ...]
    | IN GROUP rolename [, ...]
    | ROLE rolename [, ...]
    | ADMIN rolename [, ...]
    | USER rolename [, ...]
    | SYSID uid
```

CREATE INDEX

Defines a new index.

```
CREATE [UNIQUE] INDEX name ON table
   [USING btree|bitmap|gist]
   ( {column | (expression)} [opclass] [, ...] )
   [ WITH ( FILLFACTOR = value ) ]
   [TABLESPACE tablespace]
   [WHERE predicate]
```

CREATE LANGUAGE

Defines a new procedural language.

```
CREATE [PROCEDURAL] LANGUAGE name

CREATE [TRUSTED] [PROCEDURAL] LANGUAGE name

HANDLER call handler [VALIDATOR valfunction]
```

CREATE OPERATOR

Defines a new operator.

```
CREATE OPERATOR name (
PROCEDURE = funcname
[, LEFTARG = lefttype] [, RIGHTARG = righttype]
[, COMMUTATOR = com_op] [, NEGATOR = neg_op]
[, RESTRICT = res_proc] [, JOIN = join_proc]
[, HASHES] [, MERGES]
[, SORT1 = left_sort_op] [, SORT2 = right_sort_op]
[, LTCMP = less than op] [, GTCMP = greater than op] )
```

CREATE OPERATOR CLASS

```
Defines a new operator class.
```

```
CREATE OPERATOR CLASS name [DEFAULT] FOR TYPE data type
 USING index method AS
 OPERATOR strategy_number op_name [(op_type, op_type)] [RECHECK]
  | FUNCTION support number function (argument type [, ...] )
  | STORAGE storage type
  } [, ...]
```

CREATE RESOURCE QUEUE

Defines a new resource queue.

```
where queue attribute is:
  ACTIVE STATEMENTS=integer
        [ MAX COST=float [COST OVERCOMMIT={TRUE|FALSE}] ]
        [ MIN COST=float ]
        [ PRIORITY={MIN|LOW|MEDIUM|HIGH|MAX} ]
        [ MEMORY LIMIT='memory units' ]
MAX COST=float [ COST OVERCOMMIT={TRUE|FALSE} ]
        [ ACTIVE STATEMENTS=integer ]
        [ MIN COST=float ]
        [ PRIORITY={MIN|LOW|MEDIUM|HIGH|MAX} ]
        [ MEMORY LIMIT='memory units' ]
```

CREATE RESOURCE QUEUE name WITH (queue attribute=value [, ...])

CREATE ROLE

Defines a new database role (user or group).

```
CREATE ROLE name [[WITH] option [ ... ]]
where option can be:
```

```
SUPERUSER | NOSUPERUSER
| CREATEDB | NOCREATEDB
| CREATEROLE | NOCREATEROLE
| CREATEEXTTABLE | NOCREATEEXTTABLE
  [ ( attribute='value'[, ...] ) ]
      where attributes and values are:
      type='readable'|'writable'
      protocol='qpfdist'|'http'|'qphdfs'
```

```
| LOGIN | NOLOGIN
```

| INHERIT | NOINHERIT

| CONNECTION LIMIT connlimit

| RESOURCE QUEUE queue name

```
| [ ENCRYPTED | UNENCRYPTED ] PASSWORD 'password'
| VALID UNTIL 'timestamp'
| IN ROLE rolename [, ...]
| ROLE rolename [, ...]
| ADMIN rolename [, ...]
```

CREATE RULE

Defines a new rewrite rule.

```
CREATE [OR REPLACE] RULE name AS ON event
 TO table [WHERE condition]
 DO [ALSO | INSTEAD] { NOTHING | command | (command; command ...) }
```

CREATE SCHEMA

Defines a new schema.

```
CREATE SCHEMA schema_name [AUTHORIZATION username] [schema_element [ ... ]]
CREATE SCHEMA AUTHORIZATION rolename [schema_element [ ... ]]
```

CREATE SEQUENCE

Defines a new sequence generator.

```
CREATE [TEMPORARY | TEMP] SEQUENCE name
[INCREMENT [BY] value]
[MINVALUE minvalue | NO MINVALUE]
[MAXVALUE maxvalue | NO MAXVALUE]
[START [ WITH ] start]
[CACHE cache]
[[NO] CYCLE]
[OWNED BY { table.column | NONE }]
```

CREATE TABLE

Defines a new table.

```
CREATE [[GLOBAL | LOCAL] {TEMPORARY | TEMP}] TABLE table name (
       [ { column name data type [DEFAULT default expr]
           [column constraint [ ... ]]
           | table constraint
           | LIKE other table [{INCLUDING | EXCLUDING}
                                {DEFAULTS | CONSTRAINTS}] ...}
           [, ...] )
   [ INHERITS ( parent table [, ... ] ) ]
   [ WITH ( storage parameter=value [, ... ] )
   [ ON COMMIT {PRESERVE ROWS | DELETE ROWS | DROP} ]
   [ TABLESPACE tablespace ]
   [ DISTRIBUTED BY (column, [ ... ] ) | DISTRIBUTED RANDOMLY ]
   [ PARTITION BY partition type (column)
       [ SUBPARTITION BY partition type (column) ]
          [ SUBPARTITION TEMPLATE ( template spec ) ]
       [...]
    ( partition spec )
        | [ SUBPARTITION BY partition type (column) ]
          [...]
    ( partition spec
      [ ( subpartition_spec
           [(...)]
         ) ]
where storage parameter is:
  APPENDONLY={TRUE | FALSE}
  ORIENTATION={COLUMN | ROW}
  COMPRESSTYPE={ZLIB|QUICKLZ}
  COMPRESSLEVEL={0-9 | 1}
  FILLFACTOR={10-100}
  OIDS [=TRUE | FALSE]
where column constraint is:
   [CONSTRAINT constraint name]
  NOT NULL | NULL
   | UNIQUE [USING INDEX TABLESPACE tablespace]
            [WITH ( FILLFACTOR = value )]
   | PRIMARY KEY [USING INDEX TABLESPACE tablespace]
                 [WITH ( FILLFACTOR = value )]
   | CHECK ( expression )
and table constraint is:
   [CONSTRAINT constraint name]
  UNIQUE ( column name [, ... ] )
          [USING INDEX TABLESPACE tablespace]
          [WITH ( FILLFACTOR=value )]
   | PRIMARY KEY ( column name [, ... ] )
                 [USING INDEX TABLESPACE tablespace]
                 [WITH ( FILLFACTOR=value )]
   | CHECK ( expression )
where partition type is:
   LIST
  | RANGE
where partition specification is:
```

```
partition element [, ...]
and partition element is:
  DEFAULT PARTITION name
  | [PARTITION name] VALUES (list value [,...] )
  | [PARTITION name]
    START ([datatype] 'start value') [INCLUSIVE | EXCLUSIVE]
    [ END ([datatype] 'end_value') [INCLUSIVE | EXCLUSIVE] ]
     [ EVERY ([datatype] [number | INTERVAL] 'interval value') ]
  | [PARTITION name]
    END ([datatype] 'end value') [INCLUSIVE | EXCLUSIVE]
     [ EVERY ([datatype] [number | INTERVAL] 'interval value') ]
[ WITH ( partition storage parameter=value [, ... ] ) ]
[ TABLESPACE tablespace ]
where subpartition spec or template spec is:
subpartition element [, ...]
and subpartition element is:
  DEFAULT SUBPARTITION name
  | [SUBPARTITION name] VALUES (list\_value [,...] )
  | [SUBPARTITION name]
    START ([datatype] 'start value') [INCLUSIVE | EXCLUSIVE]
    [ END ([datatype] 'end value') [INCLUSIVE | EXCLUSIVE] ]
    [ EVERY ([datatype] [number | INTERVAL] 'interval value') ]
  | [SUBPARTITION name]
    END ([datatype] 'end value') [INCLUSIVE | EXCLUSIVE]
     [ EVERY ([datatype] [number | INTERVAL] 'interval value') ]
[ WITH ( partition storage parameter=value [, ... ] ) ]
[ TABLESPACE tablespace ]
CREATE TABLE AS
Defines a new table from the results of a query.
CREATE [ [GLOBAL | LOCAL] {TEMPORARY | TEMP} ] TABLE table name
  [(column name [, ...])]
   [ WITH ( storage parameter=value [, ... ] ) ]
   [ON COMMIT {PRESERVE ROWS | DELETE ROWS | DROP}]
   [TABLESPACE tablespace]
  AS query
   [DISTRIBUTED BY (column, [ ... ] ) | DISTRIBUTED RANDOMLY]
where storage parameter is:
  APPENDONLY={TRUE|FALSE}
  ORIENTATION={COLUMN|ROW}
  COMPRESSTYPE = { ZLIB | QUICKLZ }
  COMPRESSLEVEL={0-9 | 1}
  FILLFACTOR={10-100}
  OIDS [=TRUE | FALSE]
CREATE TABLESPACE
Defines a new tablespace.
CREATE TABLESPACE tablespace name [OWNER username]
       FILESPACE filespace name
```

CREATE TRIGGER

Defines a new trigger. User-defined triggers are not supported in Greenplum Database.

```
CREATE TRIGGER name {BEFORE | AFTER} {event [OR ...]}
ON table [ FOR [EACH] {ROW | STATEMENT} ]
EXECUTE PROCEDURE function ( arguments )
```

CREATE TYPE

Defines a new data type.

```
CREATE TYPE name AS ( attribute_name data_type [, ...])

CREATE TYPE name (

INPUT = input_function,

OUTPUT = output_function

[, RECEIVE = receive_function]

[, SEND = send_function]

[, ANALYZE = analyze_function]

[, INTERNALLENGTH = {internallength | VARIABLE}]

[, PASSEDBYVALUE]

[, ALIGNMENT = alignment]

[, STORAGE = storage]

[, DEFAULT = default]

[, ELEMENT = element]

[, DELIMITER = delimiter]
)

CREATE TYPE name
```

CREATE USER

Defines a new database role with the LOGIN privilege by default.

```
CREATE USER name [ [WITH] option [ ... ] ]
where option can be:
     SUPERUSER | NOSUPERUSER
    | CREATEDB | NOCREATEDB
    | CREATEROLE | NOCREATEROLE
    | CREATEUSER | NOCREATEUSER
    | INHERIT | NOINHERIT
    | LOGIN | NOLOGIN
    | [ ENCRYPTED | UNENCRYPTED ] PASSWORD 'password'
    | VALID UNTIL 'timestamp'
    | IN ROLE rolename [, ...]
    | IN GROUP rolename [, ...]
    | ROLE rolename [, ...]
    | ADMIN rolename [, ...]
    | USER rolename [, ...]
    | SYSID uid
    | RESOURCE QUEUE queue name
```

CREATE VIEW

Defines a new view.

DEALLOCATE

Deallocates a prepared statement.

```
DEALLOCATE [PREPARE] name
```

DECLARE

Defines a cursor.

```
DECLARE name [BINARY] [INSENSITIVE] [NO SCROLL] CURSOR [{WITH | WITHOUT} HOLD] FOR query [FOR READ ONLY]
```

DELETE

Deletes rows from a table.

```
DELETE FROM [ONLY] table [[AS] alias]
[USING usinglist]
[WHERE condition]
```

DROP AGGREGATE

Removes an aggregate function.

```
DROP AGGREGATE [IF EXISTS] name ( type [, ...] ) [CASCADE | RESTRICT]
```

DROP CAST

Removes a cast.

```
DROP CAST [IF EXISTS] (sourcetype AS targettype) [CASCADE | RESTRICT]
```

DROP CONVERSION

Removes a conversion.

```
DROP CONVERSION [IF EXISTS] name [CASCADE | RESTRICT]
```

DROP DATABASE

Removes a database.

```
DROP DATABASE [IF EXISTS] name
```

DROP DOMAIN

Removes a domain.

```
DROP DOMAIN [IF EXISTS] name [, ...] [CASCADE | RESTRICT]
```

DROP EXTERNAL TABLE

Removes an external table definition.

```
DROP EXTERNAL [WEB] TABLE [IF EXISTS] name [CASCADE | RESTRICT]
```

DROP FILESPACE

Removes a filespace.

```
DROP FILESPACE [IF EXISTS] filespacename
```

DROP FUNCTION

Removes a function.

```
DROP FUNCTION [IF EXISTS] name ( [ [argmode] [argname] argtype [, \dots] ) [CASCADE | RESTRICT]
```

DROP GROUP

Removes a database role.

```
DROP GROUP [IF EXISTS] name [, ...]
```

DROP INDEX

Removes an index

```
DROP INDEX [IF EXISTS] name [, ...] [CASCADE | RESTRICT]
```

DROP LANGUAGE

Removes a procedural language.

```
DROP [PROCEDURAL] LANGUAGE [IF EXISTS] name [CASCADE | RESTRICT]
```

DROP OPERATOR

Removes an operator.

```
DROP OPERATOR [IF EXISTS] name ( \{lefttype \mid NONE\} , \{righttype \mid NONE\} ) [CASCADE | RESTRICT]
```

DROP OPERATOR CLASS

Removes an operator class.

```
DROP OPERATOR CLASS [IF EXISTS] name USING index_method [CASCADE | RESTRICT]
```

DROP OWNED

Removes database objects owned by a database role.

```
DROP OWNED BY name [, ...] [CASCADE | RESTRICT]
```

DROP RESOURCE QUEUE

Removes a resource queue.

```
DROP RESOURCE QUEUE queue name
```

DROP ROLE

Removes a database role.

```
DROP ROLE [IF EXISTS] name [, ...]
```

DROP RULE

Removes a rewrite rule.

```
DROP RULE [IF EXISTS] name ON relation [CASCADE | RESTRICT]
```

DROP SCHEMA

Removes a schema.

```
DROP SCHEMA [IF EXISTS] name [, ...] [CASCADE | RESTRICT]
```

DROP SEQUENCE

Removes a sequence.

```
DROP SEQUENCE [IF EXISTS] name [, ...] [CASCADE | RESTRICT]
```

DROP TABLE

Removes a table.

```
DROP TABLE [IF EXISTS] name [, ...] [CASCADE | RESTRICT]
```

DROP TABLESPACE

Removes a tablespace.

DROP TABLESPACE [IF EXISTS] tablespacename

DROP TRIGGER

Removes a trigger.

```
DROP TRIGGER [IF EXISTS] name ON table [CASCADE | RESTRICT]
```

DROP TYPE

Removes a data type.

```
DROP TYPE [IF EXISTS] name [, ...] [CASCADE | RESTRICT]
```

DROP USER

Removes a database role.

```
DROP USER [IF EXISTS] name [, ...]
```

DROP VIEW

Removes a view.

```
DROP VIEW [IF EXISTS] name [, ...] [CASCADE | RESTRICT]
```

END

Commits the current transaction.

```
END [WORK | TRANSACTION]
```

EXECUTE

Executes a prepared SQL statement.

```
EXECUTE name [ (parameter [, \dots] ) ]
```

EXPLAIN

Shows the query plan of a statement.

```
EXPLAIN [ANALYZE] [VERBOSE] statement
```

FETCH

```
Retrieves rows from a query using a cursor.
```

```
FETCH [ forward_direction { FROM | IN } ] cursorname

where forward_direction can be empty or one of:

NEXT
FIRST
LAST
ABSOLUTE count
RELATIVE count
count
ALL
FORWARD
FORWARD count
FORWARD ALL
```

GRANT

Defines access privileges.

```
GRANT { {SELECT | INSERT | UPDATE | DELETE | REFERENCES | TRIGGER} [,...] | ALL [PRIV-
ILEGES] }
    ON [TABLE] tablename [, ...]
   TO {rolename | PUBLIC} [, ...] [WITH GRANT OPTION]
GRANT { {USAGE | SELECT | UPDATE} [,...] | ALL [PRIVILEGES] }
    ON SEQUENCE sequencename [, ...]
    TO { rolename | PUBLIC } [, ...] [WITH GRANT OPTION]
GRANT { {CREATE | CONNECT | TEMPORARY | TEMP} [,...] | ALL [PRIVILEGES] }
   ON DATABASE dbname [, ...]
   TO {rolename | PUBLIC} [, ...] [WITH GRANT OPTION]
GRANT { EXECUTE | ALL [PRIVILEGES] }
   ON FUNCTION function ( [ [argmode] [argname] argtype [, \dots] ] ) [, \dots]
   TO {rolename | PUBLIC} [, ...] [WITH GRANT OPTION]
GRANT { USAGE | ALL [PRIVILEGES] }
   ON LANGUAGE languame [, ...]
   TO {rolename | PUBLIC} [, ...] [WITH GRANT OPTION]
GRANT { {CREATE | USAGE} [,...] | ALL [PRIVILEGES] }
   ON SCHEMA schemaname [, ...]
    TO {rolename | PUBLIC} [, ...] [WITH GRANT OPTION]
GRANT { CREATE | ALL [PRIVILEGES] }
   ON TABLESPACE tablespacename [, ...]
   TO {rolename | PUBLIC} [, ...] [WITH GRANT OPTION]
GRANT parent role [, ...]
      TO member role [, ...] [WITH ADMIN OPTION]
```

INSERT

Creates new rows in a table.

```
INSERT INTO table [( column [, ...] )] { DEFAULT VALUES | VALUES ( {expression | DEFAULT} [, ...] ) [, ...] | query}
```

LOAD

Loads or reloads a shared library file.

```
LOAD 'filename'
```

LOCK

Locks a table.

```
LOCK [TABLE] name [, ...] [IN lockmode MODE] [NOWAIT]

where lockmode is one of:

ACCESS SHARE | ROW SHARE | ROW EXCLUSIVE | SHARE UPDATE EXCLUSIVE | SHARE | SHARE ROW

EXCLUSIVE | EXCLUSIVE | ACCESS EXCLUSIVE
```

MOVE

Positions a cursor.

```
MOVE [ forward_direction {FROM | IN} ] cursorname

where direction can be empty or one of:

NEXT

FIRST

LAST

ABSOLUTE count

RELATIVE count

count

ALL

FORWARD

FORWARD count
```

PREPARE

Prepare a statement for execution.

```
PREPARE name [ (datatype [, ...] ) ] AS statement
```

REASSIGN OWNED

FORWARD ALL

Changes the ownership of database objects owned by a database role.

```
REASSIGN OWNED BY old role [, ...] TO new role
```

REINDEX

Rebuilds indexes.

```
REINDEX {INDEX | TABLE | DATABASE | SYSTEM} name
```

RELEASE SAVEPOINT

Destroys a previously defined savepoint.

```
RELEASE [SAVEPOINT] savepoint name
```

RESET

Restores the value of a system configuration parameter to the default value.

```
RESET configuration_parameter
RESET ALL
```

REVOKE

Removes access privileges.

```
REVOKE [GRANT OPTION FOR] { {SELECT | INSERT | UPDATE | DELETE
       | REFERENCES | TRIGGER | [,...] | ALL [PRIVILEGES] |
      ON [TABLE] tablename [, ...]
      FROM {rolename | PUBLIC} [, ...]
       [CASCADE | RESTRICT]
REVOKE [GRANT OPTION FOR] { {USAGE | SELECT | UPDATE} [,...]
      | ALL [PRIVILEGES] }
      ON SEQUENCE sequencename [, ...]
      FROM { rolename | PUBLIC } [, ...]
      [CASCADE | RESTRICT]
REVOKE [GRANT OPTION FOR] { {CREATE | CONNECT
      | TEMPORARY | TEMP} [,...] | ALL [PRIVILEGES] }
      ON DATABASE dbname [, ...]
      FROM {rolename | PUBLIC} [, ...]
      [CASCADE | RESTRICT]
REVOKE [GRANT OPTION FOR] {EXECUTE | ALL [PRIVILEGES]}
      ON FUNCTION function ([[argmode] [argname] argtype
                             [, \ldots]]
      FROM {rolename | PUBLIC} [, ...]
      [CASCADE | RESTRICT]
REVOKE [GRANT OPTION FOR] {USAGE | ALL [PRIVILEGES]}
      ON LANGUAGE languame [, ...]
      FROM {rolename | PUBLIC} [, ...]
      [ CASCADE | RESTRICT ]
REVOKE [GRANT OPTION FOR] { {CREATE | USAGE} [,...]
      | ALL [PRIVILEGES] }
      ON SCHEMA schemaname [, ...]
      FROM {rolename | PUBLIC} [, ...]
      [CASCADE | RESTRICT]
REVOKE [GRANT OPTION FOR] { CREATE | ALL [PRIVILEGES] }
      ON TABLESPACE tablespacename [, ...]
      FROM { rolename | PUBLIC } [, ...]
       [CASCADE | RESTRICT]
REVOKE [ADMIN OPTION FOR] parent role [, ...]
      FROM member role [, ...]
       [CASCADE | RESTRICT]
```

ROLLBACK

Aborts the current transaction.

```
ROLLBACK [WORK | TRANSACTION]
```

ROLLBACK TO SAVEPOINT

Rolls back the current transaction to a savepoint.

```
ROLLBACK [WORK | TRANSACTION] TO [SAVEPOINT] savepoint name
```

SAVEPOINT

Defines a new savepoint within the current transaction.

```
SAVEPOINT savepoint name
```

SELECT

Retrieves rows from a table or view.

```
SELECT [ALL | DISTINCT [ON (expression [, ...])]]
  * | expression [[AS] output name] [, ...]
  [FROM from item [, ...]]
  [WHERE condition]
  [GROUP BY grouping element [, ...]]
  [HAVING condition [, ...]]
  [WINDOW window name AS (window specification)]
  [{UNION | INTERSECT | EXCEPT} [ALL] select]
  [ORDER BY expression [ASC | DESC | USING operator] [, ...]]
  [LIMIT {count | ALL}]
  [OFFSET start]
  [FOR {UPDATE | SHARE} [OF table name [, ...]] [NOWAIT] [...]]
where grouping element can be one of:
  expression
 ROLLUP (expression [,...])
 CUBE (expression [,...])
 GROUPING SETS ((grouping element [, ...]))
where window specification can be:
  [window name]
  [PARTITION BY expression [, ...]]
  [ORDER BY expression [ASC | DESC | USING operator] [, ...]
     [{RANGE | ROWS}
          { UNBOUNDED PRECEDING
          | expression PRECEDING
          | CURRENT ROW
          | BETWEEN window frame bound AND window frame bound }]]
    where window frame bound can be one of:
      UNBOUNDED PRECEDING
      expression PRECEDING
     CURRENT ROW
      expression FOLLOWING
     UNBOUNDED FOLLOWING
where from item can be one of:
[ONLY] table name [[AS] alias [( column alias [, ...] )]]
(select) [AS] alias [( column alias [, ...] )]
function_name ( [argument [, ...]] ) [AS] alias
             [( column_alias [, ...]
                | column definition [, ...] )]
function_name ( [argument [, ...]] ) AS
              ( column definition [, ...] )
from item [NATURAL] join type from item
          [ON join condition | USING ( join column [, ...] )]
```

SELECT INTO

Defines a new table from the results of a query.

```
SELECT [ALL | DISTINCT [ON ( expression [, ...] )]]
 * | expression [AS output_name] [, ...]
INTO [TEMPORARY | TEMP] [TABLE] new_table
  [FROM from_item [, ...]]
  [WHERE condition]
  [GROUP BY expression [, ...]]
  [HAVING condition [, ...]]
  [UNION | INTERSECT | EXCEPT} [ALL] select]
  [ORDER BY expression [ASC | DESC | USING operator] [, ...]]
  [LIMIT {count | ALL}]
  [OFFSET start]
  [FOR {UPDATE | SHARE} [OF table_name [, ...]] [NOWAIT] [...]]
```

SET

Changes the value of a Greenplum Database configuration parameter.

```
SET [SESSION | LOCAL] configuration_parameter {TO | =} value | 'value' | DEFAULT}
SET [SESSION | LOCAL] TIME ZONE {timezone | LOCAL | DEFAULT}
```

SET ROLE

Sets the current role identifier of the current session.

```
SET [SESSION | LOCAL] ROLE rolename
SET [SESSION | LOCAL] ROLE NONE
RESET ROLE
```

SET SESSION AUTHORIZATION

Sets the session role identifier and the current role identifier of the current session.

```
SET [SESSION | LOCAL] SESSION AUTHORIZATION rolename
SET [SESSION | LOCAL] SESSION AUTHORIZATION DEFAULT
RESET SESSION AUTHORIZATION
```

SET TRANSACTION

Sets the characteristics of the current transaction.

```
SET TRANSACTION transaction_mode [, ...]

SET SESSION CHARACTERISTICS AS TRANSACTION transaction_mode [, ...]

where transaction_mode is one of:

ISOLATION LEVEL {SERIALIZABLE | REPEATABLE READ | READ COMMITTED | READ UNCOMMITTED}

READ WRITE | READ ONLY
```

SHOW

Shows the value of a system configuration parameter.

```
SHOW configuration_parameter SHOW ALL
```

START TRANSACTION

Starts a transaction block.

```
START TRANSACTION [SERIALIZABLE | REPEATABLE READ | READ COMMITTED | READ UNCOMMITTED]
```

```
[READ WRITE | READ ONLY]
```

TRUNCATE

Empties a table of all rows.

```
TRUNCATE [TABLE] name [, ...] [CASCADE | RESTRICT]
```

UPDATE

Updates rows of a table.

```
UPDATE [ONLY] table [[AS] alias]
SET {column = {expression | DEFAULT} |
  (column [, ...]) = ({expression | DEFAULT} [, ...])} [, ...]
[FROM fromlist]
[WHERE condition]
```

VACUUM

Garbage-collects and optionally analyzes a database.

```
VACUUM [FULL] [FREEZE] [VERBOSE] [table]
VACUUM [FULL] [FREEZE] [VERBOSE] ANALYZE
[table [(column [, ...])]]
```

VALUES

Computes a set of rows.

```
VALUES ( expression [, ...] ) [, ...]
[ORDER BY sort_expression [ASC | DESC | USING operator] [, ...]]
[LIMIT {count | ALL}] [OFFSET start]
```