UNIT-III

Memory Management: Background – Swapping – Contiguous memory allocation – Paging – Segmentation – Segmentation with paging. Virtual Memory: Background – Demand paging – Process creation – Page replacement – Allocation of frames – Thrashing. Case Study: Memory management in Linux


Memory Management: Background

- In general, to rum a program, it must be brought into memory.
- **Input queue** collection of processes on the disk that are waiting to be brought into memory to run the program.
- User programs go through several steps before being run
- Address binding: Mapping of instructions and data from one address to another address in memory.

Three different stages of binding:

- 1. **Compile time**: Must generate absolute code if memory location is known in prior.
- 2. **Load time**: Must generate relocatable code if memory location is not known at compile time
- 3. **Execution time**: Need hardware support for address maps (e.g., base and limit registers).

Multistep Processing of a User Program



Logical vs. Physical Address Space


- Logical address generated by the CPU; also referred to as "virtual address"
- **Physical address** address seen by the memory unit.
- Logical and physical addresses are the **same** in –compile-time and load-time address-binding schemes
- Logical (virtual) and physical addresses **differ** in –execution-time address-binding scheme

Memory-Management Unit (MMU)

- It is a hardware device that maps virtual / Logical address to physical address
- In this scheme, the relocation register's value is added to Logical address generated by a user process.
- The user program deals with *logical* addresses; it never sees the *real* physical addresses
- Logical address range: 0 to max
- Physical address range: R+0 to R+max, where R—value in relocation register

Note: relocation register is a base register.

Dynamic relocation using relocation register



Dynamic Loading

- Through this, the routine is not loaded until it is called.
 - o Better memory-space utilization; unused routine is never loaded
 - Useful when large amounts of code are needed to handle infrequently occurring cases
 - No special support from the operating system is required implemented through program design

Dynamic Linking

- Linking postponed until execution time & is particularly useful for libraries
- Small piece of code called stub, used to locate the appropriate memory-resident library routine or function.
- Stub replaces itself with the address of the routine, and executes the routine
- Operating system needed to check if routine is in processes' memory address
- **Shared libraries**: Programs linked before the new library was installed will continue using the older library

Overlays:

Downloaded from: annauniversityedu.blogspot.com


- Enable a process larger than the amount of memory allocated to it.
- At a given time, the needed instructions & data are to be kept within a memory.

Swapping

- A process can be swapped temporarily out of memory to a backing store (SWAP OUT) and then brought back into memory for continued execution (SWAP IN).
- **Backing store** fast disk large enough to accommodate copies of all memory images for all users & it must provide direct access to these memory images
- Roll out, roll in swapping variant used for priority-based scheduling algorithms; lower-priority process is swapped out so higher-priority process can be loaded and executed
- Transfer time :
 - ✓ Major part of swap time is transfer time
 - ✓ Total transfer time is directly proportional to the amount of memory swapped.
 - ✓ **Example**: Let us assume the user process is of size 1MB & the backing store is a standard hard disk with a transfer rate of 5MBPS.

Transfer time = 1000KB/5000KB per second


$$= 1/5 \text{ sec} = 200 \text{ms}$$




(i) Memory Protection:

- It should consider;
 - a) Protecting the OS from user process.
 - b) Protecting user processes from one another.
- The above protection is done by "Relocation-register & Limit-register scheme —
- Relocation register contains value of smallest physical address i.e base value.
- Limit register contains range of logical addresses each logical address must be less than the limit register

A base and a limit register define a logical address space



HW address protection with base and limit registers



Contiguous Allocation


- Each process is contained in a single contiguous section of memory.
- There are two methods namely:
 - Fixed Partition Method
 - Variable Partition Method

• Fixed – Partition Method:

- Divide memory into fixed size partitions, where each partition has exactly one process.
- The drawback is memory space unused within a partition is wasted.(eg.when process size < partition size)

Variable-partition method:

- Divide memory into variable size partitions, depending upon the size of the incoming process.
- When a process terminates, the partition becomes available for another process.
- As processes complete and leave they create holes in the main memory.
- o *Hole* block of available memory; holes of various size are scattered throughout memory.



<u>Dynamic Storage-Allocation Problem</u>:

How to satisfy a request of size _n' from a list of free holes?

Solution:

- o **First-fit**: Allocate the *first* hole that is big enough.
- o **Best-fit**: Allocate the *smallest* hole that is big enough; must search entire list, unless ordered by size. Produces the smallest leftover hole.
- o **Worst-fit**: Allocate the *largest* hole; must also search entire list. Produces the largest leftover hole.

NOTE: First-fit and best-fit are better than worst-fit in terms of speed and storage utilization

• Fragmentation:

- External Fragmentation This takes place when enough total memory space exists to satisfy a request, but it is not contiguous i.e, storage is fragmented into a large number of small holes scattered throughout the main memory.
- o **Internal Fragmentation** Allocated memory may be slightly larger than requested memory.

Example: hole = 184 bytes

Process size = 182 bytes.

We are left with a hole of 2 bytes.

Solutions:

- 1. **Coalescing :** Merge the adjacent holes together.
- 2. **Compaction:** Move all processes towards one end of memory, hole towards other end of memory, producing one large hole of available memory. This scheme is expensive as it can be done if relocation is dynamic and done at execution time.
- 3. Permit the logical address space of a process to be **non-contiguous**. This is achieved through two memory management schemes namely **paging** and **segmentation**.

Paging

- It is a memory management scheme that permits the physical address space of a process to be noncontiguous.
- It avoids the considerable problem of fitting the varying size memory chunks on to the backing store.

(i) Basic Method:


- Divide logical memory into blocks of same size called "pages".
- o Divide physical memory into fixed-sized blocks called "frames"
- o Page size is a power of 2, between 512 bytes and 16MB.

Address Translation Scheme


- o Address generated by CPU(logical address) is divided into:
 - ✓ Page number (p) used as an index into a page table which contains base address of each page in physical memory
 - ✓ Page offset (d) combined with base address to define the physical address i.e.,

Physical address = base address + offset

Paging Hardware



Paging model of logical and physical memory



Paging example for a 32-byte memory with 4-byte pages

Page size = 4 bytes

Physical memory size = 32 bytes i.e ($4 \times 8 = 32$ so, 8 pages)


Logical address $\underline{}$ 0' maps to physical address 20 i.e ((5 X 4) +0)

Where Frame no = 5, Page size = 4, Offset = 0

0 a 1 b 2 c 3 d 4 e 5 f 6 g 7 h 8 i 9 j 10 k 11 l 12 m 13 n 14 o 15 p logical memory	6 2 1	0 4 8 12	i j k l m n o p	
		20	a b c d	
		24	e f g h	
		28physical		

Allocation

- When a process arrives into the system, its size (expressed in pages) is examined.
- o Each page of process needs one frame. Thus if the process requires _n' pages, at least _n' frames must be available in memory.
- o If n' frames are available, they are allocated to this arriving process.
- The 1st page of the process is loaded into one of the allocated frames & the frame number is put into the page table.
- o Repeat the above step for the next pages & so on.



(a) Before Allocation


(b) After Allocation

Frame table: It is used to determine which frames are allocated, which frames are available, how many total frames are there, and so on.(ie) It contains all the information about the frames in the physical memory.

(ii) Hardware implementation of Page Table

- This can be done in several ways :
 - 1. Using PTBR
 - 2. TLB
- The simplest case is **Page-table base register (PTBR)**, is an index to point the page table.
- TLB (Translation Look-aside Buffer)
 - It is a fast lookup hardware cache.
 - It contains the recently or frequently used page table entries.
 - It has two parts: Key (tag) & Value.
 - More expensive.

Paging Hardware with TLB



- When a logical address is generated by CPU, its page number is presented to TLB.
- TLB hit: If the page number is found, its frame number is immediately available & is used to access memory
- o <u>TLB miss</u>: If the page number is not in the TLB, a memory reference to the page table must be made.
- o **<u>Hit ratio:</u>** Percentage of times that a particular page is found in the TLB.
 - For example hit ratio is 80% means that the desired page number in the TLB is 80% of the time.

• Effective Access Time:

- Assume hit ratio is 80%.
- If it takes 20ns to search TLB & 100ns to access memory, then the memory access takes 120ns(TLB hit)
- If we fail to find page no. in TLB (20ns), then we must 1st access memory for page table (100ns) & then access the desired byte in memory (100ns).


Therefore Total =
$$20 + 100 + 100$$

= $220 \text{ ns}(\text{TLB miss}).$

Then Effective Access Time (EAT) =
$$0.80 \text{ X} (120 + 0.20) \text{ X} 220$$
.
= 140 ns .

(iii) Memory Protection

- Memory protection implemented by associating protection bit with each frame
- o Valid-invalid bit attached to each entry in the page table:
 - ✓ "valid (v)" indicates that the associated page is in the process' logical address space, and is thus a legal page
 - ✓ "invalid (i)" indicates that the page is not in the process' logical address space



(iv) Structures of the Page Table


- a) Hierarchical Paging
- b) Hashed Page Tables
- c) Inverted Page Tables

a) **Hierarchical Paging**

o Break up the Page table into smaller pieces. Because if the page table is too large then it is quit difficult to search the page number.


Example: "Two-Level Paging "

page number		nber	page offset
	p_{i}	p_2	d
	10	10	12



Address-Translation Scheme

Address-translation scheme for a two-level 32-bit paging architecture




It requires more number of memory accesses, when the number of levels is increased.

(b) Hashed Page Tables

- o Each entry in hash table contains a linked list of elements that hash to the same location.
- o Each entry consists of;
 - (a) Virtual page numbers


- (b) Value of mapped page frame.
- (c) Pointer to the next element in the linked list.
- Working Procedure:
 - ➤ The virtual page number in the virtual address is hashed into the hash table.
 - ➤ Virtual page number is compared to field (a) in the 1st element in the linked list.
 - ➤ If there is a match, the corresponding page frame (field (b)) is used to form the desired physical address.
 - ➤ If there is no match, subsequent entries in the linked list are searched for a matching virtual page number.



<u>Clustered page table</u>: It is a variation of hashed page table & is similar to hashed page table except that each entry in the hash table refers to several pages rather than a single page.

(c) Inverted Page Table

o It has one entry for each real page (frame) of memory & each entry consists of the virtual address of the page stored in that real memory location, with information about the process that owns that page. So, only one page table is in the system.




- When a memory reference occurs, part of the virtual address ,consisting of
- <Process-id, Page-no> is presented to the memory sub-system.
- Then the inverted page table is searched for match:
 - (i) If a match is found, then the physical address is generated.
 - (ii) If no match is found, then an illegal address access has been attempted.
- o Merit: Reduce the amount of memory needed.
- o **Demerit:** Improve the amount of time needed to search the table when a page reference oocurs.

(v) Shared Pages

- o One advantage of paging is the possibility of sharing common code.
- Shared code
 - ✓ One copy of read-only (reentrant) code shared among processes (i.e., text editors, compilers, window systems).
 - ✓ Shared code must appear in same location in the logical address space of all processes
- o **Reentrant code** (**Pure code**): Non-self modifying code. If the code is reentrant, then it never changes during execution. Thus two or more processes can execute the same code at the same time.
- Private code and data
 - ✓ Each process keeps a separate copy of the code and data

✓ The pages for the private code and data can appear anywhere in the logical address space

EXAMPLE:



Drawback of Paging – Internal fragmentation

o In the worst case a process would need n pages plus one byte. It would be allocated n+1 frames resulting in an **internal fragmentation** of almost an entire frame.

Example:

Page size = 2048 bytes Process size= 72766 bytes


Process needs 35 pages plus 1086 bytes.

It is allocated 36 frames resulting in an internal fragmentation of 962 bytes.


Segmentation


- o Memory-management scheme that supports user view of memory
- A program is a collection of segments. A segment is a logical unit such as: Main program, Procedure, Function, Method, Object, Local variables, global variables, Common block, Stack, Symbol table, arrays

User's View of a Program



Logical View of Segmentation





physical memory space

Segmentation Hardware

Logical address consists of a two tuple :


<Segment-number, offset>

- Segment table maps two-dimensional physical addresses; each table entry has:
 - ✓ **Base** contains the starting physical address where the segments reside in memory
 - ✓ **Limit** specifies the length of the segment
- o Segment-table base register (STBR) points to the segment table's location in memory
- o Segment-table length register (STLR) indicates number of segments used by a program;


Segment number_s' is legal, if *s* < STLR

- o Relocation.
 - ✓ dynamic
 - ✓ by segment table
- Sharing.
 - ✓ shared segments
 - ✓ same segment number
- o Allocation.
 - ✓ first fit/best fit
 - ✓ external fragmentation
- o **Protection:** With each entry in segment table associate:
 - ✓ validation bit = $0 \Rightarrow$ illegal segment
 - ✓ read/write/execute privileges
- Protection bits associated with segments; code sharing occurs at segment level
- Since segments vary in length, memory allocation is a dynamic storageallocation problem
- A segmentation example is shown in the following diagram


Address Translation scheme



EXAMPLE:



Sharing of Segments



- O Another advantage of segmentation involves the sharing of code or data.
- Each process has a segment table associated with it, which the dispatcher uses to define the hardware segment table when this process is given the CPU.
- Segments are shared when entries in the segment tables of two different processes point to the same physical location.

Segmentation with paging

- O The IBM OS/ 2.32 bit version is an operating system running on top of the Intel 386 architecture. The 386 uses segmentation with paging for memory management. The maximum number of segments per process is 16 KB, and each segment can be as large as 4 gigabytes.
- The local-address space of a process is divided into two partitions.
 - The first partition consists of up to 8 KB segments that are private to that process.

- The second partition consists of up to 8KB segments that are shared among all the processes.
- Information about the first partition is kept in the local descriptor table (LDT), information about the second partition is kept in the global descriptor table (GDT).
- Each entry in the LDT and GDT consist of 8 bytes, with detailed information about a particular segment including the base location and length of the segment.


The logical address is a pair (selector, offset) where the selector is a16-bit number:

S	g	p
13	1	2

Where s designates the segment number, g indicates whether the segment is in the GDT or LDT, and p deals with protection. The offset is a 32-bit number specifying the location of the byte within the segment in question.

- The base and limit information about the segment in question are used to generate a linear-address.
- First, the limit is used to check for address validity. If the address is not valid, a memory fault is generated, resulting in a trap to the operating system. If it is valid, then the value of the offset is added to the value of the base, resulting in a 32-bit linear address. This address is then translated into a physical address.
- The linear address is divided into a page number consisting of 20 bits, and a page offset consisting of 12 bits. Since we page the page table, the page number is further divided into a 10-bit page directory pointer and a 10-bit page table pointer. The logical address is as follows.

p_1	p_2	d
10	10	12




- To improve the efficiency of physical memory use. Intel 386 page tables can
 be swapped to disk. In this case, an invalid bit is used in the page directory
 entry to indicate whether the table to which the entry is pointing is in memory
 or on disk.
- o If the table is on disk, the operating system can use the other 31 bits to specify the disk location of the table; the table then can be brought into memory on demand.

Virtual Memory

- o It is a technique that allows the execution of processes that may not be completely in main memory.
- Advantages:
 - ✓ Allows the program that can be larger than the physical memory.
 - ✓ Separation of user logical memory from physical memory
 - ✓ Allows processes to easily share files & address space.
 - ✓ Allows for more efficient process creation.
- o Virtual memory can be implemented using

- ✓ Demand paging
- ✓ Demand segmentation


Virtual Memory That is Larger than Physical Memory



Demand Paging

- o It is similar to a paging system with swapping.
- o Demand Paging Bring a page into memory only when it is needed
- To execute a process, swap that entire process into memory. Rather than swapping the entire process into memory however, we use -Lazy Swapper
- o **Lazy Swapper** Never swaps a page into memory unless that page will be needed.
- Advantages
 - ✓ Less I/O needed
 - ✓ Less memory needed
 - ✓ Faster response
 - ✓ More users

Transfer of a paged memory to contiguous disk space




Basic Concepts:

- Instead of swapping in the whole processes, the pager brings only those necessary pages into memory. Thus,
 - 1. It avoids reading into memory pages that will not be used anyway.
 - 2. Reduce the swap time.
 - 3. Reduce the amount of physical memory needed.
- o To differentiate between those pages that are in memory & those that are on the disk we use the **Valid-Invalid bit**

Valid-Invalid bit

- A valid invalid bit is associated with each page table entry.
- Valid → associated page is in memory.
 In-Valid →
 - ✓ invalid page
 - ✓ valid page but is currently on the disk


Page table when some pages are not in main memory



Page Fault

Access to a page marked invalid causes a page fault trap.

Steps in Handling a Page Fault



- 1. Determine whether the reference is a valid or invalid memory access
- 2. a) If the reference is invalid then terminate the process.
 - **b**) If the reference is valid then the page has not been yet brought into main memory.
- 3. Find a free frame.
- 4. Read the desired page into the newly allocated frame.
- 5. Reset the page table to indicate that the page is now in memory.
- 6. Restart the instruction that was interrupted.

Pure demand paging

- Never bring a page into memory until it is required.
- o We could start a process with no pages in memory.
- When the OS sets the instruction pointer to the 1st instruction of the process, which is on the non-memory resident page, then the process immediately faults for the page.
- After this page is bought into the memory, the process continue to execute, faulting as necessary until every page that it needs is in memory.

Performance of demand paging

- Let p be the probability of a page fault $0 \le p \le 1$
- Effective Access Time (EAT) $EAT = (1 - p) \times ma + p \times page fault time.$

Where ma \rightarrow memory access, p \rightarrow Probability of page fault $(0 \le p \le 1)$

- The memory access time denoted ma is in the range 10 to 200 ns.
- \circ If there are no page faults then EAT = ma.
- o To compute effective access time, we must know how much time is needed to service a page fault.
- o A page fault causes the following sequence to occur:
 - 1. Trap to the OS
 - 2. Save the user registers and process state.
 - 3. Determine that the interrupt was a page fault.
 - 4. Check whether the reference was legal and find the location of page on disk.
 - 5. Read the page from disk to free frame.
 - a. Wait in a queue until read request is serviced.
 - b. Wait for seek time and latency time.
 - c. Transfer the page from disk to free frame.
 - 6. While waiting ,allocate CPU to some other user.
 - 7. Interrupt from disk.
 - 8. Save registers and process state for other users.
 - 9. Determine that the interrupt was from disk.
 - 7. Reset the page table to indicate that the page is now in memory.
 - 8. Wait for CPU to be allocated to this process again.
 - 9. Restart the instruction that was interrupted.

Process Creation

- o Virtual memory enhances the performance of creating and running processes:
 - Copy-on-Write
 - Memory-Mapped Files

a) Copy-on-Write

- o **fork**() creates a child process as a duplicate of the parent process & it worked by creating copy of the parent address space for child, duplicating the pages belonging to the parent.
- o **Copy-on-Write** (**COW**) allows both parent and child processes to initially *share* the same pages in memory. These shared pages are marked as Copy-on-Write pages, meaning that if either process modifies a shared page, a copy of the shared page is created.
- o vfork():
 - With this the parent process is suspended & the child process uses the address space of the parent.

- Because vfork() does not use Copy-on-Write, if the child process changes any pages of the parent's address space, the altered pages will be visible to the parent once it resumes.
- Therefore, vfork() must be used with caution, ensuring that the child process does not modify the address space of the parent.

(b) Memory – mapped files:


- Sequential read of a file on disk uses open(), read() and write()
- o Every time a file is accessed it requires a system call and disk access.
- o Alternative method: "Memory mapped files"
 - Allowing a part of virtual address space to be logically associated with file
 - Mapping a disk block to a page in memory.

Page Replacement

- o If no frames are free, we could find one that is not currently being used & free it.
- We can free a frame by writing its contents to swap space & changing the page table to indicate that the page is no longer in memory.
- Then we can use that freed frame to hold the page for which the process faulted.

Basic Page Replacement

- 1. Find the location of the desired page on disk
- 2. Find a free frame
 - If there is a free frame, then use it.
 - If there is no free frame, use a page replacement algorithm to select a **victim** frame
- Write the victim page to the disk, change the page & frame tables accordingly.
- 3. Read the desired page into the (new) free frame. Update the page and frame tables.
- 4. Restart the process



Note:

If no frames are free, two page transfers are required & this situation effectively doubles the page- fault service time.


Modify (dirty) bit:

- It indicates that any word or byte in the page is modified.
- When we select a page for replacement, we examine its modify bit.
 - If the bit is set, we know that the page has been modified & in this case we must write that page to the disk.
 - If the bit is not set, then if the copy of the page on the disk has not been overwritten, then we can avoid writing the memory page on the disk as it is already there.

Page Replacement Algorithms

- 1. FIFO Page Replacement
- 2. Optimal Page Replacement
- 3. LRU Page Replacement
- 4. LRU Approximation Page Replacement
- 5. Counting-Based Page Replacement
- o We evaluate an algorithm by running it on a particular string of memory references & computing the number of page faults. The string of memory reference is called a −reference string. The algorithm that provides less number of page faults is termed to be a good one.

 As the number of available frames increases, the number of page faults decreases. This is shown in the following graph:




(a) FIFO page replacement algorithm

- o Replace the oldest page.
- This algorithm associates with each page ,the time when that page was brought in.

Example:

Reference string: 7,0,1,2,0,3,0,4,2,3,0,3,2,1,2,0,1,7,0,1

No. of available frames = 3 (3 pages can be in memory at a time per process)



No. of page faults = 15

Drawback:

- o FIFO page replacement algorithm _s performance is not always good.
- o To illustrate this, consider the following example:

Reference string: 1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5


- o If No. of available frames -= 3 then the no. of page faults =9
- o If No.of available frames =4 then the no.of page faults =10
- Here the no. of page faults increases when the no. of frames increases . This is called as **Belady's Anomaly.**

(b) Optimal page replacement algorithm

• Replace the page that will not be used for the longest period of time. Example:

Reference string: 7,0,1,2,0,3,0,4,2,3,0,3,2,1,2,0,1,7,0,1

No. of available frames = 3



No. of page faults = 9

Drawback:


 It is difficult to implement as it requires future knowledge of the reference string.

(c) LRU(Least Recently Used) page replacement algorithm

• Replace the page that has not been used for the longest period of time. Example:

Reference string: 7,0,1,2,0,3,0,4,2,3,0,3,2,1,2,0,1,7,0,1

No. of available frames = 3



No. of page faults = 12

o LRU page replacement can be implemented using


1. Counters

- ✓ Every page table entry has a time-of-use field and a clock or counter is associated with the CPU.
- ✓ The counter or clock is incremented for every memory reference.
- ✓ Each time a page is referenced, copy the counter into the timeof-use field.
- ✓ When a page needs to be replaced, replace the page with the smallest counter value.

2. Stack

- ✓ Keep a stack of page numbers
- ✓ Whenever a page is referenced, remove the page from the stack and put it on top of the stack.
- ✓ When a page needs to be replaced, replace the page that is at the bottom of the stack.(LRU page)

Use of A Stack to Record The Most Recent Page References



(d) LRU Approximation Page Replacement

- o Reference bit
 - \checkmark With each page associate a reference bit, initially set to 0
 - \checkmark When page is referenced, the bit is set to 1
- o When a page needs to be replaced, replace the page whose reference bit is 0
- o The order of use is not known, but we know which pages were used and which were not used.

(i) Additional Reference Bits Algorithm

- Keep an 8-bit byte for each page in a table in memory.
- o At regular intervals, a timer interrupt transfers control to OS.
- The OS shifts reference bit for each page into higher- order bit shifting the other bits right 1 bit and discarding the lower-order bit.


Example:

- o If reference bit is 00000000 then the page has not been used for 8 time periods.
- o If reference bit is 111111111 then the page has been used atleast once each time period.
- o If the reference bit of page 1 is 11000100 and page 2 is 01110111 then page 2 is the LRU page.

(ii) Second Chance Algorithm

- o Basic algorithm is FIFO
- o When a page has been selected, check its reference bit.
 - ✓ If 0 proceed to replace the page
 - ✓ If 1 give the page a second chance and move on to the next FIFO page.

- ✓ When a page gets a second chance, its reference bit is cleared and arrival time is reset to current time.
- ✓ Hence a second chance page will not be replaced until all other pages are replaced.



(iii) Enhanced Second Chance Algorithm

- o Consider both reference bit and modify bit
- o There are four possible classes

0

- 1. (0,0) neither recently used nor modified \rightarrow Best page to replace
- 2. (0,1) not recently used but modified \rightarrow page has to be written out before replacement.
- 3. (1,0) recently used but not modified \rightarrow page may be used again
- 4. (1,1) recently used and modified \rightarrow page may be used again and page has to be written to disk

(e) Counting-Based Page Replacement

- Keep a counter of the number of references that have been made to each page
 - 1. Least Frequently Used (LFU)Algorithm: replaces page with smallest count
 - 2. **Most Frequently Used (MFU)Algorithm**: replaces page with largest count
 - ✓ It is based on the argument that the page with the smallest count was probably just brought in and has yet to be used

Page Buffering Algorithm

• These are used along with page replacement algorithms to improve their performance

Technique 1:

- o A pool of free frames is kept.
- o When a page fault occurs, choose a victim frame as before.
- o Read the desired page into a free frame from the pool
- The victim frame is written onto the disk and then returned to the pool of free frames.

Technique 2:

- Maintain a list of modified pages.
- Whenever the paging device is idles, a modified is selected and written to disk and its modify bit is reset.

Technique 3:

- o A pool of free frames is kept.
- o Remember which page was in each frame.
- o If frame contents are not modified then the old page can be reused directly from the free frame pool when needed

Allocation of Frames

- There are two major allocation schemes
 - ✓ Equal Allocation
 - ✓ Proportional Allocation
- o Equal allocation
 - ✓ If there are n processes and m frames then allocate m/n frames to each process.
 - ✓ **Example:** If there are 5 processes and 100 frames, give each process 20 frames.

o Proportional allocation

✓ Allocate according to the size of process

Let s_i be the size of process i.

Let m be the total no. of frames

Then
$$S = \sum s_i$$

$$a_i = s_i / S * m$$


where a_i is the no.of frames allocated to process i.

Global vs. Local Replacement

- o **Global replacement** each process selects a replacement frame from the set of all frames; one process can take a frame from another.
- Local replacement each process selects from only its own set of allocated frames.

Thrashing

- o High paging activity is called **thrashing**.
- o If a process does not have -enough pages, the page-fault rate is very high. This leads to:
 - ✓ low CPU utilization
 - ✓ operating system thinks that it needs to increase the degree of multiprogramming
 - ✓ another process is added to the system
- When the CPU utilization is low, the OS increases the degree of multiprogramming.
- o If global replacement is used then as processes enter the main memory they tend to steal frames belonging to other processes.
- Eventually all processes will not have enough frames and hence the page fault rate becomes very high.
- o Thus swapping in and swapping out of pages only takes place.
- o This is the cause of thrashing.




- o To **limit thrashing**, we can use a **local replacement** algorithm.
- o To prevent thrashing, there are two methods namely ,
 - ✓ Working Set Strategy

✓ Page Fault Frequency


1. Working-Set Strategy

- o It is based on the assumption of the model of locality.
- o Locality is defined as the set of pages actively used together.
- \circ Working set is the set of pages in the most recent Δ page references
- \circ Δ is the working set window.
 - \checkmark if \triangle too small, it will not encompass entire locality
 - \checkmark if \triangle too large ,it will encompass several localities
 - ✓ if $\Delta = \infty \Rightarrow$ it will encompass entire program
- O $D = \Sigma WSS_i$
 - ✓ Where WSS_i is the working set size for process i.
 - ✓ D is the total demand of frames
- o if D > m then Thrashing will occur.



2. Page-Fault Frequency Scheme

- o If actual rate too low, process loses frame
- o If actual rate too high, process gains frame



Other Issues

Prepaging

- ✓ To reduce the large number of page faults that occurs at process startup
- ✓ Prepage all or some of the pages a process will need, before they are referenced
- ✓ But if prepaged pages are unused, I/O and memory are wasted

o Page Size

Page size selection must take into consideration:

- fragmentation
- o table size
- o I/O overhead
- locality

TLB Reach

- ✓ TLB Reach The amount of memory accessible from the TLB
- ✓ TLB Reach = (TLB Size) X (Page Size)
- ✓ Ideally, the working set of each process is stored in the TLB. Otherwise there is a high degree of page faults.
- ✓ Increase the Page Size. This may lead to an increase in fragmentation as not all applications require a large page size
- ✓ Provide Multiple Page Sizes. This allows applications that require larger page sizes the opportunity to use them without an increase in fragmentation.

I/O interlock

- ✓ Pages must sometimes be locked into memory
- ✓ Consider I/O. Pages that are used for copying a file from a device must be

locked from being selected for eviction by a page replacement algorithm.