Faust Standard Libraries

Contents

Faust Libraries 10
Using the Faust Libraries
Contributing
New Functions
New Libraries
General Organization
Coding Conventions
Documentation
Library Import
"Demo" Functions
The question of licensing/authoring/copyrigth
Standard Functions 16
Analysis Tools
Basic Elements
Conversion
Effects
Envelope Generators
Filters
Oscillators/Sound Generators
Synths
analyzer.lib 19
Amplitude Tracking
amp_follower
amp_follower_ud 20
amp_follower_ar 21
Spectrum-Analyzers
mth_octave_analyzer
Mth-Octave Spectral Level
mth_octave_spectral_level6e
[third half]_octave_[analyzer filterbank] 23
Arbritary-Crossover Filter-Banks and Spectrum Analyzers
analyzer 23

basic.lib	24
Conversion Tools	24
samp2sec	24
sec2samp	25
db21inear	25
linear2db	25
lin2LogGain	25
log2LinGain	26
tau2pole	26
pole2tau	26
midikey2hz	27
pianokey2hz	27
hz2pianokey	27
Counters and Time/Tempo Tools	28
countdown	28
countup	28
sweep	28
time	29
tempo	29
period	29
pulse	30
pulsen	30
beat	30
<pre>pulse_countup</pre>	30
pulse_countdown	31
pulse_countup_loop	31
<pre>pulse_countdown_loop</pre>	31
Array Processing/Pattern Matching	32
count	32
take	32
subseq	32
Selectors (Conditions)	33
if	33
selector	33
selectn	34
select2stereo	34
Other	34
latch	34
sAndH	35
peakhold	35
peakholder	35
impulsify	36
automat	36
bpf	36
bypass1	37
bypass2	37

toggle				37
on_and_off			. :	38
selectoutn			. :	38
101				
compressor.lib				39
Functions Reference				39
compressor_mono				39
compressor_stereo				39
limiter_1176_R4_mono				40
limiter_1176_R4_stereo				41
delay.lib			2	41
Basic Delay Functions				41
delay				41
fdelay			-	42
sdelay				42
Lagrange Interpolation				43
-				43
fdelaylti and fdelayltv				43
fdelay[n]				
Thiran Allpass Interpolation				43
fdelay[n]a		•	•	44
demo.lib			4	44
Analyzers				45
mth_octave_spectral_level_demo				45
Filters				45
parametric_eq_demo				45
spectral_tilt_demo				45
•				45
mth octave filterbank demo and filterbank demo				-
<pre>mth_octave_filterbank_demo and filterbank_demo</pre>				46
Effects				46 46
Effects				46
Effects	 	· ·		46 46
Effects cubicnl_demo gate_demo compressor_demo	 			46 46 46
Effects				46 46 46 46
Effects				46 46 46 46 47
Effects cubicnl_demo gate_demo compressor_demo exciter moog_vcf_demo wah4_demo	· · · · · · · · · ·			46 46 46 46 47 47
Effects cubicnl_demo gate_demo compressor_demo exciter moog_vcf_demo wah4_demo crybaby_demo				46 46 46 46 47 47
Effects cubicnl_demo gate_demo compressor_demo exciter moog_vcf_demo wah4_demo crybaby_demo vocoder_demo				46 46 46 46 47 47 47
Effects cubicnl_demo gate_demo compressor_demo exciter moog_vcf_demo wah4_demo crybaby_demo vocoder_demo flanger_demo				46 46 46 47 47 47 47 48
Effects cubicnl_demo gate_demo compressor_demo exciter moog_vcf_demo wah4_demo crybaby_demo vocoder_demo flanger_demo phaser2_demo				46 46 46 47 47 47 47 48 48
Effects cubicnl_demo gate_demo compressor_demo exciter moog_vcf_demo wah4_demo crybaby_demo vocoder_demo flanger_demo phaser2_demo freeverb_demo				46 46 46 47 47 47 47 48 48 48
Effects cubicnl_demo gate_demo compressor_demo exciter moog_vcf_demo wah4_demo crybaby_demo vocoder_demo flanger_demo phaser2_demo freeverb_demo stereo_reverb_tester				46 46 46 47 47 47 47 48 48 48
Effects cubicnl_demo gate_demo compressor_demo exciter moog_vcf_demo wah4_demo crybaby_demo vocoder_demo flanger_demo phaser2_demo freeverb_demo stereo_reverb_tester fdnrev0_demo				46 46 46 47 47 47 47 48 48 48 49
Effects cubicnl_demo gate_demo compressor_demo exciter moog_vcf_demo wah4_demo crybaby_demo vocoder_demo flanger_demo phaser2_demo freeverb_demo stereo_reverb_tester				46 46 46 47 47 47 47 48 48 48
Effects cubicnl_demo gate_demo compressor_demo exciter moog_vcf_demo wah4_demo crybaby_demo vocoder_demo flanger_demo phaser2_demo freeverb_demo stereo_reverb_tester fdnrev0_demo				46 46 46 47 47 47 47 48 48 48 49

	sawtooth_demo
	virtual_analog_oscillator_demo 50
	oscrs_demo
envelop	e.lib 50
Func	tions Reference
	$\verb smoothEnvelope $
	ar 51
	asr
	adsr
filter.li	52
Basi	e Filters
	zero
	pole
	integrator
	dcblockerat 54
	dcblocker
Com	b Filters
	ff_comb
	ff_fcomb
	ffcombfilter
	fb_comb
	fb_fcomb
	rev1
	fbcombfilter and ffbcombfilter
	allpass_comb
	allpass_fcomb
	rev2
	allpass_fcomb5 and allpass_fcomb1a 59
Dire	et-Form Digital Filter Sections
	iir
	fir
	conv and convN
	tf1, tf2 and tf3
	notchw
Dire	et-Form Second-Order Biquad Sections 61
	tf21, tf22, tf22t and tf21t 62
Lado	ler/Lattice Digital Filters
	av2sv
	bvav2nuv
	iir_lat2
	allpassnt
	iir_kl
	allpassnklt
	iir lat1 64

allpassn1mt					65
iir_nl					65
allpassnnlt					66
Useful Special Cases					66
tf2np					66
wgr					66
nlf2					67
apnl					67
Ladder/Lattice Allpass Filters					68
allpassn					68
allpassnn					69
allpasskl					69
allpass1m					69
Digital Filter Sections Specified as Analog Filter Sections					70
tf2s and tf2snp					70
tf3slf					71
tf1s					71
tf2sb					72
tf1sb					72
Simple Resonator Filters					72
resonlp					72
resonhp					73
resonbp					73
Butterworth Lowpass/Highpass Filters					74
lowpass					74
highpass					74
lowpass0_highpass1					75
Special Filter-Bank Delay-Equalizing Allpass Filters					75
lowpass_plus minus_highpass					75
Elliptic (Cauer) Lowpass Filters					75
lowpass3e					75
lowpass6e					76
Elliptic Highpass Filters					76
highpass3e					76
highpass6e					77
Butterworth Bandpass/Bandstop Filters					77
bandpass					77
bandstop					77
Elliptic Bandpass Filters					78
bandpass6e					78
bandpass12e					78
Parametric Equalizers (Shelf, Peaking)					78
low_shelf					79
high_shelf					79
peak_eq					80
peak ed cd	•	 •	•	•	80
		 			()()

<pre>peak_eq_rm</pre>	
levelfilter	
<pre>levelfilterN</pre>	
Mth-Octave Filter-Banks	
<pre>mth_octave_filterbank[n]</pre>	
Arbritary-Crossover Filter-Banks and Spectrum Analy	
filterbank	
filterbanki	
TIIOOIDamii	
hoa.lib	
encoder	
decoder	
decoderStereo	
Optimization Functions	
optimBasic	
optimMaxRe	
optimInPhase	
Usage	
wider	
map	
rotate	
math.lib	
Functions Reference	
SR	
BS	
PI	
FTZ	
neg	
$\operatorname{sub}(x,y)$	
SHD(X,V)	
inv	
inv cbrt hypot ldexp scalb log1p logb ilogb	
inv	
inv. cbrt hypot ldexp scalb log1p logb ilogb cypm1 acosh	
inv	
inv. cbrt hypot ldexp scalb log1p logb ilogb cypm1 acosh	

	tanh	94
	erf	94
	erfc	94
	gamma	94
	lgamma	95
	J0	95
	J1	95
	Jn	95
	YO	96
	Y1	96
	Yn	96
	fabs, fmax, fmin	96
	np2	97
	frac	97
		97
	isnan	98
	chebychev	98
	chebychevpoly	98
	diffn	90
misceffe	ect lib	99
		99
Бупс		99
		100
	9 =	100
Filto	0 =	101
1 1100.		101
	•	101
		101
Time	-	102
1 11116		
D:+ ol		102
P ItCI.	<u> </u>	103
N f = -1-	•	103
Mesn		103
	mesh_square	103
miscoso	cillator.lib 1	04
	e-Table-Based Oscillators	
wave		105
		105
		105
	1	105
		106
	±	106
LEO		106
LFO		107 107
	it imperain	1117

1f_pulsetrainpos 107 1f_squarewavepos 107 1f_squarewave 108 1f_trianglepos 108 1f_triangle 108 Low Frequency Sawtooths 109 1f_rawsaw 109 1f_sawpos 109 1f_saw 110 1f_saw 110 1f_sawpos_phase 110 Bandlimited Sawtooth 112 sawN 112 sawNp 112 saw2dpw 112 saw3 112 saw2f2 113 saw2f2 113 saw2f4 113 Bandlimited Pulse, Square, and Impulse Trains 113 pulsetrain 114 squareN 114 impulsetrain 114 imptrain 115 triangleN 116 oscr 117 osc 118 oscr 117 osc		
1f_squarewave 108 1f_trianglepos 108 1f_triangle 108 Low Frequency Sawtooths 109 1f_rawsaw 109 1f_sawpos 109 1f_saw 110 1f_sawo 110 Bandlimited Sawtooth 110 sawN 112 saw2dpw 112 saw2dpw 112 saw2dpw 112 saw2f2 113 sawtooth 112 saw2f2 113 saw2f4 113 Bandlimited Pulse, Square, and Impulse Trains 113 pulsetrain 114 square 114 impulsetrain 114 impulsetrain 114 imptrain 115 triangle 115 triangle 115 triangle 115 file oscrs 117 osc 118 oscs 118 oscs 118	lf_pulsetrainpos	107
T_trianglepos 108	lf_squarewavepos	107
If_triangle 108 Low Frequency Sawtooths 109 lf_rawsaw 109 lf_sawpos 109 lf_sawpos 110 lf_sawpos_phase 110 Bandlimited Sawtooth 110 sawN 112 sawNp 112 saw2dpw 112 saw2dpw 112 saw2fo 113 saw2f1 113 saw2f2 113 saw2f4 113 Bandlimited Pulse, Square, and Impulse Trains 113 pulsetrain 113 pulsetrain 114 squareN 114 impulse 114 imptrain 115 triangleN 115 triangleN 115 Filter-Based Oscillators 116 oscr 117 osc 118 oscr 117 osc 118 oscr 118 oscr 118 oscw 118 oscw 118	lf_squarewave	108
Low Frequency Sawtooths 109 1f_rawsaw 109 1f_rawsaw 109 1f_sawpos 109 1f_saw 110 110 1f_sawpos_phase 110 Bandlimited Sawtooth 110 sawN 112 sawNp 112 saw2dpw 112 saw2dpw 112 saw2dpw 112 saw3 112 saw2f2 113 saw2f4 113 Bandlimited Pulse, Square, and Impulse Trains 113 pulsetrainN 113 pulsetrainN 114 squareN 114 squareN 114 squareN 114 simptrainN 115 triangleN 115 triangleN 115 triangleN 115 triangleN 115 triangleN 115 triangleN 116 oscb 116 oscr 117 oscr 117 oscr 118 oscw 118 oscw 118 oscw 118 oscw 118 oscw 119 os	lf_trianglepos	108
lf_rawsaw 109 lf_sawpos 109 lf_saw 110 lf_sawpos_phase 110 Bandlimited Sawtooth 110 sawN 112 sawNp 112 saw2dpw 112 saw3 112 saw4f2 113 saw2f4 113 Bandlimited Pulse, Square, and Impulse Trains 113 pulsetrainN 113 pulsetrain 114 squareN 114 impulse 114 imptrain 115 triangleN 115 triangleN 115 triangle Oscillators 116 oscb 116 oscr 117 osc 118 oscr 118 oscw 118 oscw 119	lf_triangle	108
1f_sawpos. 109 1f_saw 110 1f_sawpos_phase 110 Bandlimited Sawtooth 110 sawN 112 sawNp 112 saw2dpw 112 saw2dpw 112 saw3 112 saw2dp 113 saw2f2 113 saw2f4 113 Bandlimited Pulse, Square, and Impulse Trains 113 pulsetrain 113 pulsetrain 114 square 114 impulse 114 imptrain 115 triangle 115 triangle 115 triangle 115 triangle 115 triangle 116 oscb 116 oscr 117 osc 118 oscr 117 osc 118 oscr 118 oscr 118 oscr 118 oscr 118 oscr 119	Low Frequency Sawtooths	109
1f_saw 110 1f_sawpos_phase 110 Bandlimited Sawtooth 112 sawN 112 sawNp 112 saw2dpw 112 saw2dpw 112 saw3 112 saw3 112 saw2f2 113 saw2f4 113 Bandlimited Pulse, Square, and Impulse Trains 113 pulsetrainN 113 pulsetrain 114 squareN 114 square 114 impulse 114 imptrain 115 triangleN 115 triangleN 115 triangle N 115 file-based Oscillators 116 oscrq 116 oscrq 117 oscc 117 osc 118 waveguide-Resonator-Based Oscilators 118 oscw 118 oscw 118 oscw 119 oscw 119 oscw 119 <	lf_rawsaw	109
1f_sawpos_phase 110 Bandlimited Sawtooth 110 sawN 112 sawNp 112 saw2dpw 112 saw3 112 sawtooth 112 saw2f2 113 saw2f4 113 Bandlimited Pulse, Square, and Impulse Trains 113 pulsetrainN 113 pulsetrain 114 squareN 114 impulse 114 imptrain 115 triangleN 115 triangleN 115 triangle 115 Filter-Based Oscillators 116 oscr 117 osc 117 oscr 117 osc 118 oscs 118 waveguide-Resonator-Based Oscilators 118 oscw 118 oscw 119 oscw 119 oscw 119 oscw 119 oscw 119 oscw 119	lf_sawpos	109
Bandlimited Sawtooth 110 sawN 112 sawNp 112 saw2dpw 112 saw3 112 sawtooth 112 saw2f2 113 saw2f4 113 Bandlimited Pulse, Square, and Impulse Trains 113 pulsetrainN 113 pulsetrain 114 squareN 114 impulse 114 imptrain 115 triangleN 115 triangle 115 Filter-Based Oscillators 116 oscb 116 oscre 117 osc 118 oscs 118 waveguide-Resonator-Based Oscilators 118 oscw 118 oscw 119 oscw </td <td>lf_saw</td> <td>110</td>	lf_saw	110
sawN 112 sawNp 112 saw2dpw 112 saw3 112 sawtooth 112 saw2f2 113 saw2f4 113 Bandlimited Pulse, Square, and Impulse Trains 113 pulsetrainN 113 pulsetrain 114 squareN 114 impulse 114 imptrain 115 triangleN 115 triangle 115 Filter-Based Oscillators 116 oscb 116 oscrq 116 oscrs 117 osc 118 oscs 118 oscs 118 oscw 118 oscw 118 oscw 119 oscw 119 oscw 119 oscw 119 oscw 119 osc 120 noise 120 multirandom 120	lf_sawpos_phase	110
sawNp 112 saw2dpw 112 saw3 112 sawtooth 112 saw2f2 113 saw2f4 113 Bandlimited Pulse, Square, and Impulse Trains 113 pulsetrainN 113 pulsetrain 114 squareN 114 impulse 114 imptrain 115 triangleN 115 triangle Stillators 116 oscb 116 oscrq 116 oscr 117 oscr 117 oscr 118 waveguide-Resonator-Based Oscilators 118 oscw 118 oscw 119 osc 120 multirandom 120	Bandlimited Sawtooth	110
saw2dpw 112 saw3 112 sawtooth 112 saw2f2 113 saw2f4 113 Bandlimited Pulse, Square, and Impulse Trains 113 pulsetrainN 113 pulsetrain 114 squareN 114 impulse 114 impulse 114 imptrainN 115 triangleN 115 triangle Oscillators 116 oscb 116 oscrq 116 oscrq 116 oscrs 117 osc 118 oscs 118 oscw 118 oscw 119 oscw 119 <td< td=""><td>sawN</td><td>112</td></td<>	sawN	112
saw3 112 saw2f2 113 saw2f4 113 Bandlimited Pulse, Square, and Impulse Trains 113 pulsetrainN 113 pulsetrain 114 squareN 114 impulse 114 imptrainN 115 imptrain 115 triangleN 115 triangle 115 Filter-Based Oscillators 116 oscb 116 oscrq 116 oscrs 117 osc 118 oscs 118 waveguide-Resonator-Based Oscilators 118 oscw 118 oscw 119 oscw 120<	sawNp	112
sawtooth 112 saw2f2 113 saw2f4 113 Bandlimited Pulse, Square, and Impulse Trains 113 pulsetrainN 113 pulsetrain 114 squareN 114 impulse 114 imptrainN 115 imptrain 115 triangleN 115 triangle Stile 115 Filter-Based Oscillators 116 oscb 116 oscrq 116 oscrs 117 osc 117 osc 118 oscs 118 waveguide-Resonator-Based Oscilators 118 oscws 119 oscw	saw2dpw	112
saw2f2 113 saw2f4 113 Bandlimited Pulse, Square, and Impulse Trains 113 pulsetrainN 113 pulsetrain 114 squareN 114 impulse 114 imptrainN 115 imptrain 115 triangleN 115 triangle Selletors 116 oscb 116 oscrq 116 oscrs 117 osc 118 oscs 118 oscs 118 oscs 118 oscw 118 oscws 119 oscw 119 oscw <td>saw3</td> <td>112</td>	saw3	112
saw2f4 113 Bandlimited Pulse, Square, and Impulse Trains 113 pulsetrainN 113 pulsetrain 114 squareN 114 impulse 114 impulse 114 imptrainN 115 imptrain 115 triangleN 115 triangle 115 Filter-Based Oscillators 116 oscb 116 oscrq 116 oscrs 117 osc c 117 osc c 118 oscs 118 oscw 118 oscw 119	sawtooth	112
Bandlimited Pulse, Square, and Impulse Trains 113 pulsetrainN 113 pulsetrain 114 squareN 114 impulse 114 impulse 114 imptrainN 115 imptrain 115 triangleN 115 triangle 115 Filter-Based Oscillators 116 oscb 116 oscrq 116 oscrs 117 oscrc 117 osc 118 oscs 118 waveguide-Resonator-Based Oscilators 118 oscw 119 oscw 119<	saw2f2	113
pulsetrainN 113 pulsetrain 114 squareN 114 impulse 114 imptrainN 115 imptrain 115 triangleN 115 triangle 115 Filter-Based Oscillators 116 oscb 116 oscrq 116 oscrs 117 oscrc 117 osc 118 oscs 118 waveguide-Resonator-Based Oscilators 118 oscw 119 oscwq 119 oscw 120 moise 120 multirandom 120	saw2f4	113
pulsetrain 114 squareN 114 impulse 114 imptrainN 115 imptrain 115 triangleN 115 triangle 115 Filter-Based Oscillators 116 oscb 116 oscrq 116 oscrs 117 oscrc 117 osc 118 oscs 118 Waveguide-Resonator-Based Oscilators 118 oscw 118 oscws 119 oscw 120 moise 120 multirandom 120	Bandlimited Pulse, Square, and Impulse Trains	113
squareN 114 square 114 impulse 114 imptrainN 115 imptrain 115 triangleN 115 triangle 115 Filter-Based Oscillators 116 oscb 116 oscrq 116 oscrs 117 oscr 117 osc 118 oscs 118 Waveguide-Resonator-Based Oscilators 118 oscw 118 oscws 119 oscw 120 noise 120 multirandom 120	pulsetrainN	113
square 114 impulse 114 imptrainN 115 imptrain 115 triangleN 115 triangle 115 Filter-Based Oscillators 116 oscb 116 oscrq 116 oscrs 117 oscrc 117 osc 118 oscs 118 Waveguide-Resonator-Based Oscilators 118 oscw 118 oscws 119 oscwq 119 oscw 119 oscw 119 noise 120 multirandom 120	pulsetrain	114
impulse 114 imptrainN 115 imptrain 115 triangleN 115 triangle 115 Filter-Based Oscillators 116 oscb 116 oscrq 116 oscrs 117 oscrc 117 osc 118 oscs 118 Waveguide-Resonator-Based Oscilators 118 oscw 118 oscws 119 oscw 120 noise 120 multirandom 120	squareN	114
imptrainN 115 imptrain 115 triangleN 115 triangle 115 Filter-Based Oscillators 116 oscb 116 oscrq 116 oscrs 117 oscrc 117 osc 118 oscs 118 Waveguide-Resonator-Based Oscilators 118 oscw 118 oscws 119 oscwq 119 oscw 120 moise 120 multirandom 120	square	114
imptrain 115 triangleN 115 triangle 115 Filter-Based Oscillators 116 oscb 116 oscrq 116 oscrs 117 oscrc 117 osc 118 oscs 118 Waveguide-Resonator-Based Oscilators 118 oscw 118 oscws 119 oscwq 119 oscw 120 moise 120 multirandom 120	impulse	114
triangleN 115 triangle 115 Filter-Based Oscillators 116 oscb 116 oscrq 116 oscrs 117 oscrc 117 osc 118 oscs 118 Waveguide-Resonator-Based Oscilators 118 oscw 118 oscws 119 oscwq 119 oscw 120 moise 120 multirandom 120	imptrainN	115
triangle 115 Filter-Based Oscillators 116 oscb 116 oscrq 116 oscrs 117 oscrc 117 osc 118 oscs 118 Waveguide-Resonator-Based Oscilators 118 oscw 118 oscws 119 oscwq 119 oscw 119 oscw 119 oscw 119 oscw 120 moise 120 multirandom 120	imptrain	115
Filter-Based Oscillators 116 oscb 116 oscrq 116 oscrs 117 oscrc 117 osc 118 oscs 118 waveguide-Resonator-Based Oscilators 118 oscw 118 oscws 119 oscwq 119 oscw 119 oscw 119 oscw 119 oscw 120 moise 120 multirandom 120	triangleN	115
oscb 116 oscrq 116 oscrs 117 oscrc 117 osc 118 oscs 118 Waveguide-Resonator-Based Osccilators 118 oscw 118 oscws 119 oscwq 119 oscw 119 oscw 119 oscw 119 oscw 120 moise 120 multirandom 120	triangle	115
oscrq 116 oscrs 117 oscrc 117 osc 118 oscs 118 Waveguide-Resonator-Based Osccilators 118 oscw 118 oscws 119 oscwq 119 oscw 119 oscw 119 oscw 119 oscw 120 moise 120 multirandom 120	Filter-Based Oscillators	116
oscrs 117 oscrc 117 osc 118 oscs 118 Waveguide-Resonator-Based Osccilators 118 oscw 118 oscws 119 oscwq 119 oscw 119 oscw 119 oscw 119 oscw 120 moise 120 multirandom 120	oscb	116
oscrc 117 osc 118 oscs 118 Waveguide-Resonator-Based Oscilators 118 oscw 118 oscws 119 oscwq 119 oscw 119 oscw 119 oscw 120 functions Reference 120 noise 120 multirandom 120	oscrq	116
osc 118 oscs 118 Waveguide-Resonator-Based Oscilators 118 oscw 118 oscws 119 oscwq 119 oscw 119 oscw 119 oscw 120 Functions Reference 120 noise 120 multirandom 120	oscrs	117
oscs 118 Waveguide-Resonator-Based Oscilators 118 oscw 118 oscws 119 oscwq 119 oscw 119 oscw 119 oscw 120 Functions Reference 120 noise 120 multirandom 120	oscrc	117
Waveguide-Resonator-Based Osccilators 118 oscw 118 oscws 119 oscwq 119 oscw 119 noise.lib 120 Functions Reference 120 noise 120 multirandom 120	osc	118
oscw 118 oscws 119 oscwq 119 oscw 119 noise.lib 120 Functions Reference 120 noise 120 multirandom 120	oscs	118
oscws 119 oscwq 119 oscw 119 noise.lib 120 Functions Reference 120 noise 120 multirandom 120	Waveguide-Resonator-Based Oscillators	118
oscwq 119 oscw 119 noise.lib 120 Functions Reference 120 noise 120 multirandom 120	oscw	118
oscw 119 noise.lib 120 Functions Reference 120 noise 120 multirandom 120	oscws	119
noise.lib 120 Functions Reference 120 noise 120 multirandom 120	oscwq	119
Functions Reference <	oscw	119
Functions Reference <		
noise <td< td=""><td></td><td></td></td<>		
multirandom		
		120 191

	noises
	pink_noise
	pink_noise_vm
	lfnoise, lfnoiseO and lfnoiseN
phafla.	
Func	etions Reference
	flanger_mono
	flanger_stereo
	phaser2_mono
	phaser2_stereo
pm.lib	125
pm.mo	chain(A:B:)
	Requires
	input(x)
	output()
	terminations(a,b,c)
	Requires
	full Terminations (a,b,c)
	Requires
	$leftTermination(a,b) \dots \dots$
	Requires
	rightTermination(b,c)
	Requires
	$waveguide(nMax,n) \dots \dots$
	idealString(length, reflexion, xPosition, x)
reverb.	lib 129
runc	etions Reference
	jcrev
	satrev
	mono_freeverb
	stereo_freeverb
	fdnrev0
	zita_rev_fdn
	zita_rev1_stereo
	zita_rev1_ambi
route.li	ib 132
	etions Reference
runc	cross
	crossnn
	crossn1
	interleave
	hutterfly 134

	hadamard																				134
	recursivize																				135
	•1																				105
signal.l																					135
Func	tions Reference .																				
	bus																				
	block																				
	interpolate																				136
	smooth	-	-	-	-	 -	-	 •		-	 -	-	-	-	-	-	-	-	-	-	137
	smoo	-	-	-	-	 -	-		 -		 -	-	-	-	-	-	-	-	-	-	137
	polySmooth																				137
	bsmooth					 •			 ٠	•				•				•			138
	lag_ud								 •												138
	dot				•				 •	•						•		•			138
spat.lib	•																				139
эрасты	panner																				
	spat																				
	stereoize																				
	BUCICUIZC	•	•	•	•	 •	•	 •	 •	•	 •	•	•	•	•	•	•	•	•	•	140
synth.li	ib																				140
	<pre>popFilterPerc .</pre>																				140
	dubDub																				141
	<pre>sawTrombone</pre>																				141
	combString																				141
	additiveDrum																				142
	${\tt fm} \ \ldots \ \ldots \ \ldots$																				142
vaeffect	+ 1;h																				143
																					143
runc	tions Reference .																				
	moog_vcf																				
	moog_vcf_2b[n]																				
	wah4																				
	autowah																				
	crybaby vocoder																				

Faust Libraries

NOTE: this documentation was automatically generated.

This page provides information on how to use the Faust libraries.

The /libraries folder contains the different Faust libraries. If you wish to add your own functions to this library collection, you can refer to the "Contributing" section providing a set of coding conventions.

WARNING: These libraries replace the "old" Faust libraries. They are still being beta tested so you might encounter bugs while using them. If your codes still use the "old" Faust libraries, you might want to try to use Bart Brouns' script that automatically makes an old Faust code compatible with the new libraries: https://github.com/magnetophon/faustCompressors/blob/master/newlib.sh. If you find a bug, please report it at rmichon_at_ccrma_dot_stanford_dot_edu. Thanks;)!

Using the Faust Libraries

The easiest and most standard way to use the Faust libraries is to import stdfaust.lib in your Faust code:

```
import("stdfaust.lib");
```

This will give you access to all the Faust libraries through a series of environments:

```
• an: analyzer.lib
  • ba: basic.lib
  • co: compressor.lib
  • de: delay.lib
  • dm: demo.lib
  • en: envelope.lib
  • fi: filter.lib
  • ho: hoa.lib
  • ma: math.lib
  • ef: misceffect.lib
  • os: miscoscillator.lib
  • no: noise.lib
  • pf: phafla.lib
  • pm: pm.lib
  • re: reverb.lib
  • ro: route.lib
  • si: signal.lib
  • sp: spat.lib
  • sy: synth.lib
  • ve: vaeffect.lib
Environments can then be used as follows in your Faust code:
import("stdfaust.lib");
process = os.osc(440);
In this case, we're calling the osc function from miscoscillator.lib.
Alternatively, environments can be created by hand:
os = library("miscoscillator.lib");
process = os.osc(440);
```

Finally, libraries can be simply imported in the Faust code (not recommended):

```
import("miscoscillator.lib");
process = osc(440);
```

Contributing

If you wish to add a function to any of these libraries or if you plan to add a new library, make sure that you follow the following conventions:

New Functions

• All functions must be preceded by a markdown documentation header respecting the following format (open the source code of any of the libraries for an example):

- Every time a new function is added, the documentation should be updated simply by running make doclib.
- The environment system (e.g. os.osc) should be used when calling a function declared in another library (see the section on *Using the Faust Libraries*).
- Try to reuse exisiting functions as much as possible.
- If you have any question, send an e-mail to rmichon at ccrma dot stanford dot edu.

New Libraries

- Any new "standard" library should be declared in stdfaust.lib with its own environment (2 letters see stdfaust.lib).
- Any new "standard" library must be added to generateDoc.
- Functions must be organized by sections.
- Any new library should at least declare a name and a version.

• The comment based markdown documentation of each library must respect the following format (open the source code of any of the libraries for an example):

```
// Description
//
// * Section Name 1
// * Section Name 2
// * ...
//
// It should be used using the `[...]` environment:
// ···
// [...] = library("libraryName");
// process = [...].functionCall;
// ---
//
// Another option is to import `stdfaust.lib` which already contains the `[...]`
// environment:
//
// import("stdfaust.lib");
// process = [...].functionCall;
//======== Section Name ========
// Description
```

• If you have any question, send an e-mail to rmichon_at_ccrma_dot_stanford_dot_edu.

General Organization

Only the libraries that are considered to be "standard" are documented:

- analyzer.libbasic.lib
- compressor.lib
- delay.lib
- demo.lib
- envelope.lib
- filter.lib
- hoa.lib
- math.lib

- misceffect.lib
- miscoscillator.lib
- noise.lib
- phafla.lib
- pm.lib
- reverb.lib
- route.lib
- signal.lib
- spat.lib
- synth.lib
- tonestack.lib (not documented but example in /examples/misc)
- tube.lib (not documented but example in /examples/misc)
- vaeffect.lib

Other deprecated libraries such as music.lib, etc. are present but are not documented to not confuse new users.

The doumentation of each library can be found in /documentation/library.html or in /documentation/library.pdf.

The /examples directory contains all the examples from the /examples folder of the Faust distribution as well as new ones. Most of them were updated to reflect the coding conventions described in the next section. Examples are organized by types in different folders. The /old folder contains examples that are fully deprecated, probably because they were integrated to the libraries and fully rewritten (see freeverb.dsp for example). Examples using deprecated libraries were integrated to the general tree but a warning comment was added at their beginning to point readers to the right library and function.

Coding Conventions

In order to have a uniformized library system, we established the following conventions (that hopefully will be followed by others when making modifications to them :-)).

Documentation

- All the functions that we want to be "public" are documented.
- We used the faust2md "standards" for each library: //### for main title (library name equivalent to # in markdown), //=== for section declarations (equivalent to ## in markdown) and //--- for function declarations (equivalent to #### in markdown see basic.lib for an example).
- Sections in function documentation should be declared as #### markdown title.
- Each function documentation provides a "Usage" section (see basic.lib).

Library Import

To prevent cross-references between libraries we generalized the use of the library("") system for function calls in all the libraries. This means that everytime a function declared in another library is called, the environment corresponding to this library needs to be called too. To make things easier, a stdfaust.lib library was created and is imported by all the libraries:

```
an = library("analyzer.lib");
ba = library("basic.lib");
co = library("compressor.lib");
de = library("delay.lib");
dm = library("demo.lib");
en = library("envelope.lib");
fi = library("filter.lib");
ho = library("hoa.lib");
ma = library("math.lib");
ef = library("misceffect.lib");
os = library("miscoscillator.lib");
no = library("noise.lib");
pf = library("phafla.lib");
pm = library("pm.lib");
re = library("reverb.lib");
ro = library("route.lib");
sp = library("spat.lib");
si = library("signal.lib");
sy = library("synth.lib");
ve = library("vaeffect.lib");
For example, if we wanted to use the smooth function which is now declared in
```

signal.lib, we would do the following:

```
import("stdfaust.lib");
process = si.smooth(0.999);
```

This standard is only used within the libraries: nothing prevents coders to still import signal.lib directly and call smooth without ro., etc.

"Demo" Functions

All the functions that were present in the libraries and that contained any kind of UI elements declaration (mostly JOS "demo" functions) were turned into independent .dsp files that were placed in the /examples folder. Thus, Faust libraries now only contain "pure" function declarations which should make them more legible. Also, "demo" functions make great examples...

For practicality, the "demo" functions are still declared and are available in demo.lib as "components" pointing at the /examples folder (which is why that folder will have to be installed on the system during the installation process of the Faust distribution).

The question of licensing/authoring/copyrigth

Now that Faust libraries are not author specific, each function will be able to have its own licence/author declaration. This means that some libraries wont have a global licence/author/copyright declaration like it used to be the case.

Standard Functions

Dozens of functions are implemented in the Faust libraries and many of them are very specialized and not useful to beginners or to people who only need to use Faust for basic applications. This section offers an index organized by categories of the "standard Faust functions" (basic filters, effects, synthesizers, etc.).

Analysis Tools

Function Type	Function Name	Description
Amplitude Follower Octave Analyzers	<pre>an.amp_follower an.mth_octave_analyzer[N]</pre>	Classic analog audio envelope follower Octave analyzers

Basic Elements

Function Type	Function Name	Description
Beats	ba.beat	Pulses at a specific tempo
Block	si.block	Terminate n signals
Break Point Function	ba.bpf	Beak Point Function (BPF)
Bus	si.bus	Bus of n signals
Bypass (Mono)	ba.bypass1	Mono bypass
Bypass (Stereo)	ba.bypass2	Stereo bypass
Count Elements	ba.count	Count elements in a list
Count Down	ba.countdown	Samples count down
Count Up	ba.countup	Samples count up
Delay (Integer)	de.delay	Integer delay
Delay (Float)	de.fdelay	Fractional delay
Impulsify	ba.impulsify	Turns a signal into an impulse

Function Type	Function Name	Description
Sample and Hold	ba.sAndH	Sample and hold
Signal Crossing	ro.cross	Cross n signals
Smoother (Default)	si.smoo	Exponential smoothing
Smoother	si.smooth	Exponential smoothing with controllable pole
Take Element	ba.take	Take en element from a list
Time	ba.time	A simple timer

Conversion

Function Type	Function Name	Description
dB to Linear Linear to dB MIDI Key to Hz Pole to T60 Samples to Seconds Seconds to Samples T60 to Pole	ba.db2linear ba.linear2db ba.midikey2hz ba.pole2tau ba.samp2sec ba.sec2samp ba.tau2pole	Converts dB to linear values Converts linear values to dB Converts a MIDI key number into a frequency Converts a pole into a time constant (t60) Converts samples to seconds Converts seconds to samples Converts a time constant (t60) into a pole

Effects

Function Type	Function Name	Description
Auto Wah	ve.autowah	Auto-Wah effect
Compressor	co.compressor_mono	Dynamic range compressor
Distortion	ef.cubicnl	Cubic nonlinearity distortion
Crybaby	ve.crybaby	Crybaby wah pedal
Echo	ef.echo	Simple echo
Flanger	pf.flanger_mono	Flanging effect
Gate	ef.gate_mono	Mono signal gate
Limiter	co.limiter_1176_R4_mono	Limiter
Phaser	pf.phaser2_mono	Phaser effect
Pitch Shift	ef.transpose	Simple pitch shifter
Speaker Simulator	ef.speakerbp	Simple speaker simulator
Stereo Width	ef.stereo_width	Stereo width effect
Vocoder	ve.vocoder	Simple vocoder
Wah	ve.wah4	Wah effect

Envelope Generators

Function Type	Function Name	Description
ADSR	en.adsr	Attack/Decay/Sustain/Release envelope generator
AR	en.ar	Attack/Release envelope generator
ASR	en.asr	Attack/Sustain/Release envelope generator
Exponential	en.smoothEnvelope	Exponential envelope generator

Filters

Function Type	Function Name	Description
Bandpass (Butterworth)	fi.bandpass	Generic butterworth bandpass
Bandpass (Resonant)	fi.resonbp	Virtual analog resonant bandpass
Bandstop (Butterworth)	fi.bandstop	Generic butterworth bandstop
Biquad	fi.tf2	"Standard" biquad filter
Comb (Allpass)	fi.allpass_fcomb	Schroeder allpass comb filter
Comb (Feedback)	fi.fb_fcomb	Feedback comb filter
Comb (Feedforward)	fi.ff_fcomb	Feed-forward comb filter.
DC Blocker	fi.dcblocker	Default de blocker
Filterbank	fi.filterbank	Generic filter bank
FIR (Arbitrary Order)	fi.fir	Nth-order FIR filter
High Shelf	fi.high_shelf	High shelf
Highpass (Butterworth)	fi.highpass	Nth-order Butterworth highpass
Highpass (Resonant)	fi.resonhp	Virtual analog resonant highpass
IIR (Arbitrary Order)	fi.iir	Nth-order IIR filter
Level Filter	fi.levelfilter	Dynamic level lowpass
Low Shelf	fi.low_shelf	Low shelf
Lowpass (Butterworth)	fi.lowpass	Nth-order Butterworth lowpass
Lowpass (Resonant)	fi.resonlp	Virtual analog resonant lowpass
Notch Filter	fi.notchw	Simple notch filter
Peak Equalizer	fi.peak_eq	Peaking equalizer section

${\bf Oscillators/Sound\ Generators}$

Function Type	Function Name	Description
Impulse	os.impulse	Generate an impulse on start-up
Impulse Train	os.imptrain	Band-limited impulse train
Phasor	os.phasor	Simple phasor
Pink Noise	no.pink_noise	Pink noise generator
Pulse Train	os.pulsetrain	Band-limited pulse train
Pulse Train (Low Frequency)	os.lf_imptrain	Low-frequency pulse train
Sawtooth	os.sawtooth	Band-limited sawtooth wave
Sawtooth (Low Frequency)	os.lf_saw	Low-frequency sawtooth wave

Function Type	Function Name	Description
Sine (Filter-Based)	os.osc	Sine oscillator (filter-based)
Sine (Table-Based)	os.oscsin	Sine oscillator (table-based)
Square	os.square	Band-limited square wave
Square (Low Frequency)	os.lf_squarewave	Low-frequency square wave
Triangle	os.triangle	Band-limited triangle wave
Triangle (Low Frequency)	os.lf_triangle	Low-frequency triangle wave
White Noise	no.noise	White noise generator

Synths

Function Type	Function Name	Description
Additive Drum	sy.additiveDrum	Additive synthesis drum
Bandpassed Sawtooth	sy.dubDub	Sawtooth through resonant bandpass
Comb String	sy.combString	String model based on a comb filter
FM	sy.fm	Frequency modulation synthesizer
Lowpassed Sawtooth	sy.sawTrombone	"Trombone" based on a filtered sawtooth
Popping Filter	sy.popFilterPerc	Popping filter percussion instrument

analyzer.lib

This library contains a collection of tools to analyze signals.

It should be used using the an environment:

```
an = library("analyzer.lib");
process = an.functionCall;
```

Another option is to import stdfaust.lib which already contains the an environment:

```
import("stdfaust.lib");
process = an.functionCall;
```

Amplitude Tracking

amp_follower

Classic analog audio envelope follower with infinitely fast rise and exponential decay. The amplitude envelope instantaneously follows the absolute value going up, but then floats down exponentially. amp_follower is a standard Faust function.

```
_ : amp_follower(rel) : _
```

Where:

• rel: release time = amplitude-envelope time-constant (sec) going down

Reference

• Musical Engineer's Handbook, Bernie Hutchins, Ithaca NY, 1975 Electronotes Newsletter, Bernie Hutchins

amp_follower_ud

Envelope follower with different up and down time-constants (also called a "peak detector").

Usage

```
_ : amp_follower_ud(att,rel) : _
```

Where:

- att: attack time = amplitude-envelope time constant (sec) going up
- rel: release time = amplitude-envelope time constant (sec) going down

Note

We assume rel >> att. Otherwise, consider rel \sim max(rel,att). For audio, att is normally faster (smaller) than rel (e.g., 0.001 and 0.01). Use amp_follower_ar below to remove this restriction.

Reference

• "Digital Dynamic Range Compressor Design — A Tutorial and Analysis", by Dimitrios Giannoulis, Michael Massberg, and Joshua D. Reiss http://www.eecs.qmul.ac.uk/~josh/documents/GiannoulisMassbergReiss-dynamicrangecompression-JAES2012.pdf

amp_follower_ar

Envelope follower with independent attack and release times. The release can be shorter than the attack (unlike in amp_follower_ud above).

Usage

```
_ : amp_follower_ar(att,rel) : _;
```

Spectrum-Analyzers

Spectrum-analyzers split the input signal into a bank of parallel signals, one for each spectral band. They are related to the Mth-Octave Filter-Banks in filter.lib. The documentation of this library contains more details about the implementation. The parameters are:

- M: number of band-slices per octave (>1)
- N: total number of bands (>2)
- ftop = upper bandlimit of the Mth-octave bands ($\langle SR/2 \rangle$)

In addition to the Mth-octave output signals, there is a highpass signal containing frequencies from ftop to SR/2, and a "dc band" lowpass signal containing frequencies from 0 (dc) up to the start of the Mth-octave bands. Thus, the N output signals are

```
\label{eq:highpass} \mbox{(ftop), MthOctaveBands(M,N-2,ftop), dcBand(ftop*2^(-M*(N-1)))}
```

A Spectrum-Analyzer is defined here as any band-split whose bands span the relevant spectrum, but whose band-signals do not necessarily sum to the original signal, either exactly or to within an allpass filtering. Spectrum analyzer outputs are normally at least nearly "power complementary", i.e., the power spectra of the individual bands sum to the original power spectrum (to within some negligible tolerance).

Increasing Channel Isolation

Go to higher filter orders - see Regalia et al. or Vaidyanathan (cited below) regarding the construction of more aggressive recursive filter-banks using elliptic or Chebyshev prototype filters.

References

• "Tree-structured complementary filter banks using all-pass sections", Regalia et al., IEEE Trans. Circuits & Systems, CAS-34:1470-1484, Dec. 1987

- "Multirate Systems and Filter Banks", P. Vaidyanathan, Prentice-Hall,
- Elementary filter theory: https://ccrma.stanford.edu/~jos/filters/

mth_octave_analyzer

Octave analyzer. mth_octave_analyzer[N] are standard Faust functions.

Usage

```
_: mth_octave_analyzer(0,M,ftop,N) : par(i,N,_); // Oth-order Butterworth
_: mth_octave_analyzer6e(M,ftop,N) : par(i,N,_); // 6th-order elliptic
Also for convenience:
_: mth_octave_analyzer3(M,ftop,N) : par(i,N,_); // 3d-order Butterworth
_: mth_octave_analyzer5(M,ftop,N) : par(i,N,_); // 5th-roder Butterworth
mth_octave_analyzer_default = mth_octave_analyzer6e;
```

Where:

- O: order of filter used to split each frequency band into two
- M: number of band-slices per octave
- ftop: highest band-split crossover frequency (e.g., 20 kHz)
- N: total number of bands (including dc and Nyquist)

Mth-Octave Spectral Level

Spectral Level: Display (in bar graphs) the average signal level in each spectral band.

mth_octave_spectral_level6e

Spectral level display.

Usage:

```
_ : mth_octave_spectral_level6e(M,ftop,NBands,tau,dB_offset) : _;
```

Where:

- M: bands per octave
- ftop: lower edge frequency of top band
- NBands: number of passbands (including highpass and dc bands),

- tau: spectral display averaging-time (time constant) in seconds,
- dB_offset: constant dB offset in all band level meters.

Also for convenience:

```
mth_octave_spectral_level_default = mth_octave_spectral_level6e;
spectral_level = mth_octave_spectral_level(2,10000,20);
```

[third|half]_octave_[analyzer|filterbank]

A bunch of special cases based on the different analyzer functions described above:

```
third_octave_analyzer(N) = mth_octave_analyzer_default(3,10000,N);
third_octave_filterbank(N) = mth_octave_filterbank_default(3,10000,N);
half_octave_analyzer(N) = mth_octave_analyzer_default(2,10000,N);
half_octave_filterbank(N) = mth_octave_filterbank_default(2,10000,N);
octave_filterbank(N) = mth_octave_filterbank_default(1,10000,N);
octave_analyzer(N) = mth_octave_analyzer_default(1,10000,N);
```

Usage

See mth_octave_spectral_level_demo.

Arbritary-Crossover Filter-Banks and Spectrum Analyzers

These are similar to the Mth-octave analyzers above, except that the band-split frequencies are passed explicitly as arguments.

analyzer

Analyzer.

Usage

```
_ : analyzer(0,freqs) : par(i,N,_); // No delay equalizer Where:
```

- 0: band-split filter order (ODD integer required for filterbank[i])
- freqs: (fc1,fc2,...,fcNs) [in numerically ascending order], where Ns=N-1 is the number of octave band-splits (total number of bands N=Ns+1).

If frequencies are listed explicitly as arguments, enclose them in parens:

```
_ : analyzer(3,(fc1,fc2)) : _,_,_
```

basic.lib

A library of basic elements for Faust organized in 5 sections:

- Conversion Tools
- Counters and Time/Tempo Tools
- Array Processing/Pattern Matching
- Selectors (Conditions)
- Other Tools (Misc)

It should be used using the ba environment:

```
ba = library("basic.lib");
process = ba.functionCall;
```

Another option is to import stdfaust.lib which already contains the ba environment:

```
import("stdfaust.lib");
process = ba.functionCall;
```

Conversion Tools

samp2sec

Converts a number of samples to a duration in seconds. samp2sec is a standard Faust function.

Usage

```
samp2sec(n) : _{-}
```

Where:

• n: number of samples

se	c2	sa	mı	D
----	----	----	----	---

Converts a duration in seconds to a number of samples. samp2sec is a standard Faust function.

db2linear

Converts a loudness in dB to a linear gain (0-1). db2linear is a standard Faust function.

Usage db2linear(1) : _

Where:

• 1: loudness in dB

linear2db

Converts a linear gain (0-1) to a loudness in dB. linear2db is a standard Faust function.

Usage

```
linear2db(g) : _
Where:
     g: a linear gain
```

lin2LogGain

Converts a linear gain (0-1) to a log gain (0-1).

Usage
_ : lin2LogGain : _
log2LinGain
Converts a log gain (0-1) to a linear gain (0-1).
Usage
_ : log2LinGain : _
tau2pole
Returns a real pole giving exponential decay. Note that t60 (time to decay 60 dB) is $\sim\!6.91$ time constants. tau2pole is a standard Faust function.
Usage
_ : smooth(tau2pole(tau)) : _
Dmoodh(tdd2po10(tdd))
Where:
Where:
Where:
Where:
Where: • tau: time-constant in seconds
Where: • tau: time-constant in seconds pole2tau Returns the time-constant, in seconds, corresponding to the given real, positive
Where: • tau: time-constant in seconds pole2tau Returns the time-constant, in seconds, corresponding to the given real, positive pole in (0,1). pole2tau is a standard Faust function.
Where: • tau: time-constant in seconds pole2tau Returns the time-constant, in seconds, corresponding to the given real, positive pole in (0,1). pole2tau is a standard Faust function. Usage
Where: • tau: time-constant in seconds pole2tau Returns the time-constant, in seconds, corresponding to the given real, positive pole in (0,1). pole2tau is a standard Faust function. Usage pole2tau(pole) : _

mi			

Converts a MIDI key	number t	to a frequency	in Hz	(MIDI k	ey 69 =	A440).
midikey2hz is a stand	lard Faust	function.				

Usage
midikey2hz(mk) : _
Where:
• mk: the MIDI key number
pianokey2hz
Converts a piano key number to a frequency in Hz (piano key $49 = A440$).
Usage
pianokey2hz(pk) : _
Where:
• pk: the piano key number
hz2pianokey
Converts a frequency in Hz to a piano key number (piano key $49 = A440$).
$\mathbf{U}_{\mathbf{Sage}}$
hz2pianokey(f) : _
Where:
• f: frequency in Hz

Counters and Time/Tempo Tools

countdown

Starts counting down from n included to 0. While trig is 1 the output is n. The countdown starts with the transition of trig from 1 to 0. At the end of the countdown the output value will remain at 0 until the next trig. countdown is a standard Faust function.

Usage

countdown(n,trig) : _

Where:

- count: the starting point of the countdown
- trig: the trigger signal (1: start at n; 0: decrease until 0)

countup

Starts counting up from 0 to n included. While trig is 1 the output is 0. The countup starts with the transition of trig from 1 to 0. At the end of the countup the output value will remain at n until the next trig. countup is a standard Faust function.

Usage

countup(n,trig) : _

Where:

- count: the starting point of the countup
- trig: the trigger signal (1: start at 0; 0: increase until n)

sweep

Counts from 0 to period samples repeatedly, while run is 1. Outsputs zero while run is 0.

Usage
<pre>sweep(period,run) : _</pre>
time
A simple timer that counts every samples from the beginning of the process. time is a standard Faust function.
Usage
time : _
tempo
Converts a tempo in BPM into a number of samples.
Usage
tempo(t) : _
Where:
• t: tempo in BPM
period
Basic sawtooth wave of period p.
Usage
period(p) : _
Where:
• p: period as a number of samples

Pulses (10000) generated at period p.
Usage
<pre>pulse(p) : _</pre>
Where:
• p: period as a number of samples
pulsen
Pulses (11110000) of length n generated at period p.
Usage
<pre>pulsen(n,p) : _</pre>
Where:
• n: the length of the pulse as a number of samples
• p: period as a number of samples
beat
Pulses at tempo t. beat is a standard Faust function.
Usage
beat(t): _
Where:
• t: tempo in BPM

pulse countup

pulse

Starts counting up pulses. While trig is 1 the output is counting up, while trig is 0 the counter is reset to 0.

```
_ : pulse_countup(trig) : _
```

Where:

• trig: the trigger signal (1: start at next pulse; 0: reset to 0)

pulse_countdown

Starts counting down pulses. While trig is 1 the output is counting down, while trig is 0 the counter is reset to 0.

Usage

```
_ : pulse_countdown(trig) : _
```

Where:

• trig: the trigger signal (1: start at next pulse; 0: reset to 0)

pulse_countup_loop

Starts counting up pulses from 0 to n included. While trig is 1 the output is counting up, while trig is 0 the counter is reset to 0. At the end of the countup (n) the output value will be reset to 0.

Usage

```
_ : pulse_countup_loop(n,trig) : _
```

Where:

- n: the highest number of the countup (included) before reset to 0.
- trig: the trigger signal (1: start at next pulse; 0: reset to 0)

pulse_countdown_loop

Starts counting down pulses from 0 to n included. While trig is 1 the output is counting down, while trig is 0 the counter is reset to 0. At the end of the countdown (n) the output value will be reset to 0.

```
_ : pulse_coundown_loop(n,trig) : _
```

Where:

- n: the highest number of the countup (included) before reset to 0.
- trig: the trigger signal (1: start at next pulse; 0: reset to 0)

Array Processing/Pattern Matching

count

Count the number of elements of list l. count is a standard Faust function.

Usage

```
count(1)
count ((10,20,30,40)) -> 4
```

Where:

• 1: list of elements

take

Take an element from a list. take is a standard Faust function.

Usage

```
take(e,1)
take(3,(10,20,30,40)) -> 30
```

Where:

- p: position (starting at 1)
- 1: list of elements

subseq

Extract a part of a list.

```
subseq(1, p, n)
subseq((10,20,30,40,50,60), 1, 3) -> (20,30,40)
subseq((10,20,30,40,50,60), 4, 1) -> 50
```

Where:

- 1: list
- p: start point (0: begin of list)
- n: number of elements

Note:

Faust doesn't have proper lists. Lists are simulated with parallel compositions and there is no empty list

Selectors (Conditions)

if

if-then-else implemented with a select 2.

Usage

```
• if(c, t, e) : _
```

Where:

- c: condition
- t: signal selected while c is true
- e: signal selected while c is false

selector

Selects the ith input among n at compile time.

Usage

```
\label{eq:selector} \begin{array}{l} \texttt{selector(i,n)} \\ \texttt{\_,\_,\_,\_} : \texttt{selector(2,4)} : \texttt{\_} // \texttt{selects the 3rd input among 4} \\ \end{array} Where:
```

- i: input to select (int, numbered from 0, known at compile time)
- n: number of inputs (int, known at compile time, n > i)

selectn

Selects the ith input among N at run time.

Usage

- N: number of inputs (int, known at compile time, N > 0)
- i: input to select (int, numbered from 0)

Example test program

```
N=64;
process = par(n,N, (par(i,N,i) : selectn(N,n)));
```

select2stereo

Select between 2 stereo signals.

Usage

```
_,_,_ : select2stereo(bpc) : _,_,_,_
Where:
```

• bpc: the selector switch (0/1)

Other

latch

Latch input on positive-going transition of "clock" ("sample-and-hold").

Usage _ : latch(clocksig) : _ Where: • clocksig: hold trigger (0 for hold, 1 for bypass) sAndHSample And Hold. sAndH is a standard Faust function. Usage _ : sAndH(t) : _ Where: • t: hold trigger (0 for hold, 1 for bypass) peakhold Outputs current max value above zero. Usage _ : peakhold(mode) : _; Where: ${\tt mode}$ means: 0 - Pass through. A single sample 0 trigger will work as a reset. 1 -Track and hold max value. peakholder Tracks abs peak and holds peak for 'holdtime' samples. Usage

_ : peakholder(holdtime) : _;

impulsify

Turns the signal from a button into an impulse $(1,0,0,\ldots)$ when button turns on). impulsify is a standard Faust function.

Usage

```
button("gate") : impulsify ;
```

automat

Record and replay to the values the input signal in a loop.

Usage

```
hslider(...) : automat(bps, size, init) : _
```

bpf

bpf is an environment (a group of related definitions) that can be used to create break-point functions. It contains three functions :

- start(x,y) to start a break-point function
- end(x,y) to end a break-point function
- point(x,y) to add intermediate points to a break-point function

A minimal break-point function must contain at least a start and an end point :

```
f = bpf.start(x0,y0) : bpf.end(x1,y1);
```

A more involved break-point function can contains any number of intermediate points:

```
f = bpf.start(x0,y0) : bpf.point(x1,y1) : bpf.point(x2,y2) : bpf.end(x3,y3);
```

In any case the x_{i} must be in increasing order (for all i, x_{i} < x_{i}). For example the following definition :

```
f = bpf.start(x0,y0) : \dots : bpf.point(xi,yi) : \dots : bpf.end(xn,yn);
```

implements a break-point function f such that :

- $f(x) = y_{0} \text{ when } x < x_{0}$
- $f(x) = y_{n} \text{ when } x > x_{n}$

• $f(x) = y_{i} + (y_{i+1}-y_{i})*(x-x_{i})/(x_{i+1}-x_{i})$ when $x_{i} \le x$ and $x \le x_{i+1}$

bpf is a standard Faust function.

bypass1

Takes a mono input signal, route it to e and bypass it if bpc = 1. bypass1 is a standard Faust function.

Usage

```
_ : bypass1(bpc,e) : _
```

Where:

- bpc: bypass switch (0/1)
- e: a mono effect

bypass2

Takes a stereo input signal, route it to e and bypass it if bpc = 1. bypass2 is a standard Faust function.

Usage

```
_,_ : bypass2(bpc,e) : _,_
```

Where:

- bpc: bypass switch (0/1)
- e: a stereo effect

-

toggle

Triggered by the change of 0 to 1, it toggles the output value between 0 and 1.

${\bf Usage}$

```
_ : toggle : _
```

Examples

```
button("toggle") : toggle : vbargraph("output", 0, 1)
(an.amp_follower(0.1) > 0.01) : toggle : vbargraph("output", 0, 1) // takes audio input
```

on_and_off

The first channel set the output to 1, the second channel to 0.

Usage

```
_ , _ : on_and_off : _
```

Example

```
button("on"), button("off") : on_and_off : vbargraph("output", 0, 1)
```

selectoutn

Route input to the output among N at run time.

Usage

```
_ : selectoutn(n, s) : _,_,...n
```

Where:

- n: number of outputs (int, known at compile time, N > 0)
- s: output number to route to (int, numbered from 0) (i.e. slider)

Example

```
process = 1 : selectoutn(3, sel) : par(i,3,bar) ;
sel = hslider("volume",0,0,2,1) : int;
bar = vbargraph("v.bargraph", 0, 1);
```

compressor.lib

A library of compressor effects.

It should be used using the co environment:

```
co = library("compressor.lib");
process = co.functionCall;
```

Another option is to import stdfaust.lib which already contains the co environment:

```
import("stdfaust.lib");
process = co.functionCall;
```

Functions Reference

compressor_mono

Mono dynamic range compressors. compressor_mono is a standard Faust function

Usage

```
_ : compressor_mono(ratio,thresh,att,rel) : _
```

Where:

- ratio: compression ratio (1 = no compression, >1 means compression)
- thresh: dB level threshold above which compression kicks in (0 dB = max level)
- att: attack time = time constant (sec) when level & compression going up
- rel: release time = time constant (sec) coming out of compression

References

- http://en.wikipedia.org/wiki/Dynamic_range_compression
- https://ccrma.stanford.edu/~jos/filters/Nonlinear_Filter_Example_ Dynamic.html
- Albert Graef's "faust2pd"/examples/synth/compressor_.dsp
- More features: https://github.com/magnetophon/faustCompressors

compressor_stereo

Stereo dynamic range compressors.

```
_,_ : compressor_stereo(ratio,thresh,att,rel) : _,_
```

Where:

- ratio: compression ratio (1 = no compression, > 1 means compression)
- thresh: dB level threshold above which compression kicks in (0 dB = max level)
- att: attack time = time constant (sec) when level & compression going up
- rel: release time = time constant (sec) coming out of compression

References

- http://en.wikipedia.org/wiki/Dynamic_range_compression
- https://ccrma.stanford.edu/~jos/filters/Nonlinear_Filter_Example_ Dynamic.html
- Albert Graef's "faust2pd"/examples/synth/compressor_.dsp
- More features: https://github.com/magnetophon/faustCompressors

limiter_1176_R4_mono

A limiter guards against hard-clipping. It can be can be implemented as a compressor having a high threshold (near the clipping level), fast attack and release, and high ratio. Since the ratio is so high, some knee smoothing is desirable ("soft limiting"). This example is intended to get you started using compressor_* as a limiter, so all parameters are hardwired to nominal values here. Ratios: 4 (moderate compression), 8 (severe compression), 12 (mild limiting), or 20 to 1 (hard limiting) Att: 20-800 MICROseconds (Note: scaled by ratio in the 1176) Rel: 50-1100 ms (Note: scaled by ratio in the 1176) Mike Shipley likes 4:1 (Grammy-winning mixer for Queen, Tom Petty, etc.) Faster attack gives "more bite" (e.g. on vocals) He hears a bright, clear eq effect as well (not implemented here) limiter_1176_R4_mono is a standard Faust function.

Usage

```
_ : limiter_1176_R4_mono : _;
```

Reference:

http://en.wikipedia.org/wiki/1176_Peak_Limiter

limiter_1176_R4_stereo

A limiter guards against hard-clipping. It can be can be implemented as a compressor having a high threshold (near the clipping level), fast attack and release, and high ratio. Since the ratio is so high, some knee smoothing is desirable ("soft limiting"). This example is intended to get you started using compressor_* as a limiter, so all parameters are hardwired to nominal values here. Ratios: 4 (moderate compression), 8 (severe compression), 12 (mild limiting), or 20 to 1 (hard limiting) Att: 20-800 MICROseconds (Note: scaled by ratio in the 1176) Rel: 50-1100 ms (Note: scaled by ratio in the 1176) Mike Shipley likes 4:1 (Grammy-winning mixer for Queen, Tom Petty, etc.) Faster attack gives "more bite" (e.g. on vocals) He hears a bright, clear eq effect as well (not implemented here)

Usage

```
_,_ : limiter_1176_R4_stereo : _,_;
```

Reference:

http://en.wikipedia.org/wiki/1176 Peak Limiter

delay.lib

This library contains a collection of delay functions.

It should be used using the de environment:

```
de = library("delay.lib");
process = de.functionCall;
```

Another option is to import stdfaust.lib which already contains the de environment:

```
import("stdfaust.lib");
process = de.functionCall;
```

Basic Delay Functions

delay

Simple d samples delay where n is the maximum delay length as a number of samples (it needs to be a power of 2). Unlike the Q delay operator, this function

allows to preallocate memory which means that $\tt d$ can be changed dynamically at run time as long as it remains smaller than $\tt n$. $\tt delay$ is a standard Faust function.

Usage

 $_$: delay(n,d) : $_$

Where:

- n: the max delay length as a power of 2
- d: the delay length as a number of samples (integer)

fdelay

Simple d samples fractional delay based on 2 interpolated delay lines where ${\tt n}$ is the maximum delay length as a number of samples (it needs to be a power of 2 - see delay()). fdelay is a standard Faust function.

Usage

_ : fdelay(n,d) : _

Where:

- n: the max delay length as a power of 2
- d: the delay length as a number of samples (float)

sdelay

s(mooth)delay: a mono delay that doesn't click and doesn't transpose when the delay time is changed.

Usage

```
_ : sdelay(N,it,dt) : _
```

Where:

- N: maximal delay in samples (must be a constant power of 2, for example 65536)
- it: interpolation time (in samples) for example 1024
- dt: delay time (in samples)

Lagrange Interpolation

fdelaylti and fdelayltv

Fractional delay line using Lagrange interpolation.

Usage

_ : fdelaylt[i|v](order, maxdelay, delay, inputsignal) : _

Where order=1,2,3,... is the order of the Lagrange interpolation polynomial.

fdelaylti is most efficient, but designed for constant/slowly-varying delay. fdelayltv is more expensive and more robust when the delay varies rapidly.

NOTE: The requested delay should not be less than (N-1)/2.

References

- https://ccrma.stanford.edu/~jos/pasp/Lagrange Interpolation.html
- Timo I. Laakso et al., "Splitting the Unit Delay Tools for Fractional Delay Filter Design", IEEE Signal Processing Magazine, vol. 13, no. 1, pp. 30-60, Jan 1996.
- Philippe Depalle and Stephan Tassart, "Fractional Delay Lines using Lagrange Interpolators", ICMC Proceedings, pp. 341-343, 1996.

fdelay[n]

For convenience, fdelay1, fdelay2, fdelay3, fdelay4, fdelay5 are also available where n is the order of the interpolation.

Thiran Allpass Interpolation

Thiran Allpass Interpolation

Reference

https://ccrma.stanford.edu/~jos/pasp/Thiran_Allpass_Interpolators.html

fdelay[n]a

Delay lines interpolated using Thiran allpass interpolation.

Usage

```
_ : fdelay[N]a(maxdelay, delay, inputsignal) : _ (exactly like fdelay)
```

Where:

• N=1,2,3, or 4 is the order of the Thiran interpolation filter, and the delay argument is at least N - 1/2.

Note

The interpolated delay should not be less than $\mathbb{N}-1/2$. (The allpass delay ranges from $\mathbb{N}-1/2$ to $\mathbb{N}+1/2$.) This constraint can be alleviated by altering the code, but be aware that allpass filters approach zero delay by means of pole-zero cancellations. The delay range $[\mathbb{N}-1/2,\mathbb{N}+1/2]$ is not optimal. What is?

Delay arguments too small will produce an UNSTABLE allpass!

Because allpass interpolation is recursive, it is not as robust as Lagrange interpolation under time-varying conditions. (You may hear clicks when changing the delay rapidly.)

First-order all pass interpolation, delay d in [0.5,1.5]

demo.lib

This library contains a set of demo functions based on examples located in the /examples folder.

It should be used using the dm environment:

```
dm = library("demo.lib");
process = dm.functionCall;
```

Another option is to import stdfaust.lib which already contains the dm environment:

```
import("stdfaust.lib");
process = dm.functionCall;
```

Analyzers

mth_octave_spectral_level_demo

Demonstrate mth_octave_spectral_level in a standalone GUI.

Usage

```
_ : mth_octave_spectral_level_demo(BandsPerOctave);
_ : spectral_level_demo : _; // 2/3 octave
```

Filters

parametric_eq_demo

A parametric equalizer application.

Usage:

```
_ : parametric_eq_demo : _ ;
```

spectral_tilt_demo

A spectral tilt application.

Usage

```
_ : spectral_tilt_demo(N) : _ ;
Where:
```

• N: filter order (integer)

All other parameters interactive

${\tt mth_octave_filterbank_demo} \ \ {\tt and} \ \ {\tt filterbank_demo}$

Graphic Equalizer: Each filter-bank output signal routes through a fader.

```
_ : mth_octave_filterbank_demo(M) : _
_ : filterbank_demo : _
```

Where:

 $\bullet\,$ N: number of bands per octave

Effects

cubicnl_demo

Distortion demo application.

Usage:

```
_ : cubicnl_demo : _;
```

 ${\tt gate_demo}$

Gate demo application.

Usage

```
_,_ : gate_demo : _,_;
```

compressor_demo

Compressor demo application.

Usage

```
_,_ : compressor_demo : _,_;
```

exciter

Psychoacoustic harmonic exciter, with GUI.

Usage _ : exciter : _ References • https://secure.aes.org/forum/pubs/ebriefs/?elib=16939 $\bullet \ \, https://www.researchgate.net/publication/258333577_Modeling_the_$ ${\bf Harmonic_Exciter}$ moog_vcf_demo Illustrate and compare all three Moog VCF implementations above. Usage _ : moog_vcf_demo : _; wah4_demo Wah pedal application. Usage _ : wah4_demo : _; crybaby_demo Crybaby effect application. Usage

vocoder_demo

_ : crybaby_demo : _ ;

Use example of the vocoder function where an impulse train is used as excitation.

${\bf Usage}$

```
_ : vocoder_demo : _;
```

flanger_demo

Flanger effect application.

${\bf Usage}$

```
_,_ : flanger_demo : _,_;
```

phaser2_demo

Phaser effect demo application.

Usage

```
_,_ : phaser2_demo : _,_;
```

freeverb_demo

Freeverb demo application.

Usage

```
_,_ : freeverb_demo : _,_;
```

stereo_reverb_tester

Handy test inputs for reverberator demos below.

Usage

```
_ : stereo_reverb_tester : _
```

fdnrev0_demo

A reverb application using fdnrev0.

Usage

```
_,_ : fdnrev0_demo(N,NB,BBSO) : _,_
```

Where:

- n: Feedback Delay Network (FDN) order / number of delay lines used = order of feedback matrix / 2, 4, 8, or 16 [extend primes array below for 32, 64....]
- nb: Number of frequency bands / Number of (nearly) independent T60 controls / Integer 3 or greater
- bbso = Butterworth band-split order / order of lowpass/highpass bandsplit used at each crossover freq / odd positive integer

zita_rev_fdn_demo

Reverb demo application based on zita_rev_fdn.

Usage

```
si.bus(8) : zita_rev_fdn_demo : si.bus(8)
```

zita_rev1

Example GUI for zita_rev1_stereo (mostly following the Linux zita-rev1 GUI).

Only the dry/wet and output level parameters are "dezippered" here. If parameters are to be varied in real time, use smooth(0.999) or the like in the same way.

Usage

```
_,_ : zita_rev1 : _,_
```

Reference
http://www.kokkinizita.net/linuxaudio/zita-rev1-doc/quickguide.html
Generators
sawtooth_demo
An application demonstrating the different sawtooth oscillators of Faust
Usage
sawtooth_demo : _
virtual_analog_oscillator_demo
Virtual analog oscillator demo application.
Usage
<pre>virtual_analog_oscillator_demo : _</pre>
oscrs_demo
Simple application demoing filter based oscillators.
Usage
oscrs_demo : _

envelope.lib

This library contains a collection of envelope generators.

It should be used using the en environment:

```
en = library("envelope.lib");
process = en.functionCall;
Another option is to import stdfaust.lib which already contains the en environment:
import("stdfaust.lib");
process = en.functionCall;
```

Functions Reference

smoothEnvelope

An envelope with an exponential attack and release. smoothEnvelope is a standard Faust function.

Usage

smoothEnvelope(ar,t) : _

- ar: attack and release duration (s)
- t: trigger signal (0-1)

ar

AR (Attack, Release) envelope generator (useful to create percussion envelopes). ar is a standard Faust function.

Usage

asr

ASR (Attack, Sustain, Release) envelope generator. asr is a standard Faust function.

```
asr(a,s,r,t) :
```

Where:

- a, s, r: attack (sec), sustain (percentage of t), release (sec)
- t: trigger signal (>0 for attack, then release is when t back to 0)

adsr

ADSR (Attack, Decay, Sustain, Release) envelope generator. adsr is a standard Faust function.

Usage

```
adsr(a,d,s,r,t) : _
```

Where:

- a, d, s, r: attack (sec), decay (sec), sustain (percentage of t), release (sec)
- t: trigger signal (>0 for attack, then release is when t back to 0)

filter.lib

A library of filters and of more advanced filter-based sound processor organized in 18 sections:

- Basic Filters
- Comb Filters
- Direct-Form Digital Filter Sections
- Direct-Form Second-Order Biquad Sections
- Ladder/Lattice Digital Filters
- Useful Special Cases
- Ladder/Lattice Allpass Filters
- Digital Filter Sections Specified as Analog Filter Sections
- Simple Resonator Filters
- Butterworth Lowpass/Highpass Filters
- Special Filter-Bank Delay-Equalizing Allpass Filters
- Elliptic (Cauer) Lowpass Filters
- Elliptic Highpass Filters
- Butterworth Bandpass/Bandstop Filters
- Elliptic Bandpass Filters

- Parametric Equalizers (Shelf, Peaking)
- Mth-Octave Filter-Banks
- Arbritary-Crossover Filter-Banks and Spectrum Analyzers

It should be used using the fi environment:

```
fi = library("filter.lib");
process = fi.functionCall;
```

Another option is to import stdfaust.lib which already contains the fi environment:

```
import("stdfaust.lib");
process = fi.functionCall;
```

Basic Filters

zero

One zero filter. Difference equation: y(n) = x(n) - z * x(n-1).

Usage

```
_ : zero(z) : _
```

Where:

• z: location of zero along real axis in z-plane

Reference

 $https://ccrma.stanford.edu/\sim jos/filters/One_Zero.html$

pole

One pole filter. Could also be called a "leaky integrator". Difference equation: y(n) = x(n) + p * y(n-1).

Usage

```
_ : pole(z) : _
```

Where:

• p: pole location = feedback coefficient

Reference
$https://ccrma.stanford.edu/\sim jos/filters/One_Pole.html$
integrator
Same as pole(1) [implemented separately for block-diagram clarity].
dcblockerat
DC blocker with configurable break frequency. The amplitude response is substantially flat above fb, and sloped at about $+6$ dB/octave below fb. Derived from the analog transfer function $H(s) = s / (s + 2PIfb)$ by the low-frequency-matching bilinear transform method (i.e., the standard frequency-scaling constant 2*SR).
Usage
_ : dcblockerat(fb) : _
Where:
• fb: "break frequency" in Hz, i.e., -3 dB gain frequency.
Reference
$https://ccrma.stanford.edu/\sim jos/pasp/Bilinear_Transformation.html \\$
dcblocker
DC blocker. Default dc blocker has -3dB point near 35 Hz (at 44.1 kHz) and high-frequency gain near 1.0025 (due to no scaling). dcblocker is as standard Faust function.
Usage
_ : dcblocker : _

Comb Filters

ff_comb

Feed-Forward Comb Filter. Note that ff_comb requires integer delays (uses delay internally). ff_comb is a standard Faust function.

Usage

```
_ : ff_comb(maxdel,intdel,b0,bM) : _
```

Where:

- maxdel: maximum delay (a power of 2)
- intdel: current (integer) comb-filter delay between 0 and maxdel
- del: current (float) comb-filter delay between 0 and maxdel
- b0: gain applied to delay-line input
- bM: gain applied to delay-line output and then summed with input

Reference

 $https://ccrma.stanford.edu/\sim jos/pasp/Feedforward_Comb_Filters.html$

ff_fcomb

Feed-Forward Comb Filter. Note that ff_fcomb takes floating-point delays (uses fdelay internally). ff_fcomb is a standard Faust function.

Usage

```
_ : ff_fcomb(maxdel,del,b0,bM) : _
```

Where:

- maxdel: maximum delay (a power of 2)
- intdel: current (integer) comb-filter delay between 0 and maxdel
- del: current (float) comb-filter delay between 0 and maxdel
- b0: gain applied to delay-line input
- $\bullet\,$ bM: gain applied to delay-line output and then summed with input

Reference

 $https://ccrma.stanford.edu/\sim jos/pasp/Feedforward_Comb_Filters.html \\$

ffcombfilter

Typical special case of $ff_{comb}()$ where: b0 = 1.

fb_comb

Feed-Back Comb Filter (integer delay).

Usage

```
_ : fb_comb(maxdel,intdel,b0,aN) : _
```

Where:

- maxdel: maximum delay (a power of 2)
- intdel: current (integer) comb-filter delay between 0 and maxdel
- del: current (float) comb-filter delay between 0 and maxdel
- b0: gain applied to delay-line input and forwarded to output
- aN: minus the gain applied to delay-line output before summing with the input and feeding to the delay line

Reference

https://ccrma.stanford.edu/~jos/pasp/Feedback_Comb_Filters.html

fb_fcomb

Feed-Back Comb Filter (floating point delay).

Usage

```
_ : fb_fcomb(maxdel,del,b0,aN) : _
```

Where:

- maxdel: maximum delay (a power of 2)
- intdel: current (integer) comb-filter delay between 0 and maxdel
- del: current (float) comb-filter delay between 0 and maxdel
- b0: gain applied to delay-line input and forwarded to output
- aN: minus the gain applied to delay-line output before summing with the input and feeding to the delay line

Reference

 $https://ccrma.stanford.edu/\sim jos/pasp/Feedback_Comb_Filters.html \\$

rev1

Special case of fb_comb (rev1(maxdel,N,g)). The "rev1 section" dates back to the 1960s in computer-music reverberation. See the jcrev and brassrev in reverb.lib for usage examples.

fbcombfilter and ffbcombfilter

Other special cases of Feed-Back Comb Filter.

Usage

```
_ : fbcombfilter(maxdel,intdel,g) : _
_ : ffbcombfilter(maxdel,del,g) : _
```

Where:

- maxdel: maximum delay (a power of 2)
- intdel: current (integer) comb-filter delay between 0 and maxdel
- del: current (float) comb-filter delay between 0 and maxdel
- g: feedback gain

Reference

 $https://ccrma.stanford.edu/\sim jos/pasp/Feedback_Comb_Filters.html \\$

allpass_comb

Schroeder Allpass Comb Filter. Note that

```
allpass_comb(maxlen,len,aN) = ff_comb(maxlen,len,aN,1) : fb_comb(maxlen,len-1,1,aN); which is a direct-form-1 implementation, requiring two delay lines. The implementation here is direct-form-2 requiring only one delay line.
```

```
_ : allpass_comb (maxdel,intdel,aN) : _
```

Where:

- maxdel: maximum delay (a power of 2)
- intdel: current (integer) comb-filter delay between 0 and maxdel
- del: current (float) comb-filter delay between 0 and maxdel
- aN: minus the feedback gain

References

- https://ccrma.stanford.edu/~jos/pasp/Allpass_Two_Combs.html
- https://ccrma.stanford.edu/~jos/pasp/Schroeder_Allpass_Sections.html
- https://ccrma.stanford.edu/~jos/filters/Four_Direct_Forms.html

allpass_fcomb

Schroeder Allpass Comb Filter. Note that

```
allpass_comb(maxlen,len,aN) = ff_comb(maxlen,len,aN,1) : fb_comb(maxlen,len-1,1,aN); which is a direct-form-1 implementation, requiring two delay lines. The implementation here is direct-form-2 requiring only one delay line.
```

allpass_fcomb is a standard Faust library.

Usage

```
_ : allpass_comb (maxdel,intdel,aN) : _
_ : allpass_fcomb(maxdel,del,aN) : _
```

Where:

- maxdel: maximum delay (a power of 2)
- intdel: current (float) comb-filter delay between 0 and maxdel
- del: current (float) comb-filter delay between 0 and maxdel
- aN: minus the feedback gain

References

- https://ccrma.stanford.edu/~jos/pasp/Allpass_Two_Combs.html
- https://ccrma.stanford.edu/~jos/pasp/Schroeder_Allpass_Sections.html
- $https://ccrma.stanford.edu/\sim jos/filters/Four_Direct_Forms.html$

rev2

Special case of allpass_comb (rev2(maxlen,len,g)). The "rev2 section" dates back to the 1960s in computer-music reverberation. See the jcrev and brassrev in reverb.lib for usage examples.

allpass_fcomb5 and allpass_fcomb1a

Same as allpass_fcomb but use fdelay5 and fdelay1a internally (Interpolation helps - look at an fft of faust2octave on

```
`1-1' <: allpass_fcomb(1024,10.5,0.95), allpass_fcomb5(1024,10.5,0.95);`).
```

Direct-Form Digital Filter Sections

iir

Nth-order Infinite-Impulse-Response (IIR) digital filter, implemented in terms of the Transfer-Function (TF) coefficients. Such filter structures are termed "direct form".

iir is a standard Faust function.

Usage

```
_ : iir(bcoeffs,acoeffs) : _
```

Where:

- order: filter order (int) = max(#poles,#zeros)
- bcoeffs: $(b0,b1,...,b_order) = TF$ numerator coefficients
- acoeffs: (a1,...,a_order) = TF denominator coeffs (a0=1)

Reference

 $https://ccrma.stanford.edu/{\sim}jos/filters/Four_Direct_Forms.html$

fir

FIR filter (convolution of FIR filter coefficients with a signal)

```
_ : fir(bv) : _
```

fir is standard Faust function.

Where:

• bv = b0,b1,...,bn is a parallel bank of coefficient signals.

Note

by is processed using pattern-matching at compile time, so it must have this normal form (parallel signals).

Example

Smoothing white noise with a five-point moving average:

```
bv = .2,.2,.2,.2;
process = noise : fir(bv);
Equivalent (note double parens):
process = noise : fir((.2,.2,.2,.2));
```

conv and convN

Convolution of input signal with given coefficients.

Usage

```
_ : conv((k1,k2,k3,...,kN)) : _; // Argument = one signal bank
_ : convN(N,(k1,k2,k3,...)) : _; // Useful when N < count((k1,...))
```

tf1, tf2 and tf3

tfN = N'th-order direct-form digital filter.

```
_ : tf1(b0,b1,a1) : _
_ : tf2(b0,b1,b2,a1,a2) : _
_ : tf3(b0,b1,b2,b3,a1,a2,a3) : _
```

Where:

- a: the poles
- b: the zeros

Reference

 $https://ccrma.stanford.edu/{\sim}jos/fp/Direct_Form_I.html$

notchw

Simple notch filter based on a biquad (tf2). notchw is a standard Faust function.

Usage:

```
_ : notchw(width,freq) : _
```

Where:

- width: "notch width" in Hz (approximate)
- freq: "notch frequency" in Hz

Reference

 $https://ccrma.stanford.edu/\sim jos/pasp/Phasing_2nd_Order_Allpass_Filters. \\ html$

Direct-Form Second-Order Biquad Sections

Direct-Form Second-Order Biquad Sections

Reference

https://ccrma.stanford.edu/~jos/filters/Four_Direct_Forms.html

tf21, tf22, tf22t and tf21t

tfN = N'th-order direct-form digital filter where:

- tf21 is tf2, direct-form 1
- tf22 is tf2, direct-form 2
- tf22t is tf2, direct-form 2 transposed
- tf21t is tf2, direct-form 1 transposed

Usage

```
_ : tf21(b0,b1,b2,a1,a2) : _
_ : tf22(b0,b1,b2,a1,a2) : _
_ : tf22t(b0,b1,b2,a1,a2) : _
_ : tf21t(b0,b1,b2,a1,a2) : _
```

Where:

- a: the poles
- b: the zeros

Reference

https://ccrma.stanford.edu/~jos/fp/Direct_Form_I.html

Ladder/Lattice Digital Filters

Ladder and lattice digital filters generally have superior numerical properties relative to direct-form digital filters. They can be derived from digital waveguide filters, which gives them a physical interpretation.

av2sv

Compute reflection coefficients sv from transfer-function denominator av.

Usage

```
sv = av2sv(av)
```

Where:

- av: parallel signal bank a1,...,aN
- sv: parallel signal bank s1,...,sN

where ro = ith reflection coefficient, and ai = coefficient of $z^(-i)$ in the filter transfer-function denominator A(z).

Reference

 $https://ccrma.stanford.edu/\sim jos/filters/Step_Down_Procedure.html~(where reflection coefficients are denoted by k rather than s).$

bvav2nuv

Compute lattice tap coefficients from transfer-function coefficients.

Usage

```
nuv = bvav2nuv(bv,av)
```

Where:

- av: parallel signal bank a1,...,aN
- bv: parallel signal bank b0,b1,...,aN
- nuv: parallel signal bank nu1,...,nuN

where \mathtt{nui} is the i'th tap coefficient, \mathtt{bi} is the coefficient of $\mathtt{z}^{\texttt{(-i)}}$ in the filter numerator, \mathtt{ai} is the coefficient of $\mathtt{z}^{\texttt{(-i)}}$ in the filter denominator

iir_lat2

Two-multiply latice IIR filter or arbitrary order.

Usage

```
_ : iir_lat2(bv,av) : _
```

Where:

- $\bullet\,$ by: zeros as a bank of parallel signals
- av: poles as a bank of parallel signals

allpassnt

Two-multiply lattice allpass (nested order-1 direct-form-ii allpasses).

```
_ : allpassnt(n,sv) : _
```

Where:

- n: the order of the filter
- sv: the reflexion coefficients (-1 1)

iir_kl

Kelly-Lochbaum ladder IIR filter or arbitrary order.

Usage

```
_ : iir_kl(bv,av) : _
```

Where:

- $\bullet\,$ by: zeros as a bank of parallel signals
- av: poles as a bank of parallel signals

allpassnklt

Kelly-Lochbaum ladder allpass.

Usage:

```
_ : allpassklt(n,sv) : _
```

Where:

- n: the order of the filter
- sv: the reflexion coefficients (-1 1)

iir_lat1

One-multiply latice IIR filter or arbitrary order.

```
_ : iir_lat1(bv,av) : _
```

Where:

- bv: zeros as a bank of parallel signals
- av: poles as a bank of parallel signals

allpassn1mt

One-multiply lattice allpass with tap lines.

Usage

```
\_ : allpassn1mt(n,sv) : \_
```

Where:

- n: the order of the filter
- sv: the reflexion coefficients (-1 1)

iir_nl

Normalized ladder filter of arbitrary order.

Usage

```
_ : iir_nl(bv,av) : _
```

Where:

- bv: zeros as a bank of parallel signals
- av: poles as a bank of parallel signals

References

- J. D. Markel and A. H. Gray, Linear Prediction of Speech, New York: Springer Verlag, 1976.

allpassnnlt

Normalized ladder allpass filter of arbitrary order.

Usage:

```
\_ : allpassnnlt(n,sv) : \_
```

Where:

- n: the order of the filter
- sv: the reflexion coefficients (-1,1)

References

- J. D. Markel and A. H. Gray, Linear Prediction of Speech, New York: Springer Verlag, 1976.

Useful Special Cases

tf2np

Biquad based on a stable second-order Normalized Ladder Filter (more robust to modulation than tf2 and protected against instability).

${\bf Usage}$

```
_ : tf2np(b0,b1,b2,a1,a2) : _
```

Where:

- a: the poles
- b: the zeros

wgr

Second-order transformer-normalized digital waveguide resonator.

```
_ : wgr(f,r) : _
```

Where:

- f: resonance frequency (Hz)
- r: loss factor for exponential decay (set to 1 to make a numerically stable oscillator)

References

- https://ccrma.stanford.edu/~jos/pasp/Digital_Waveguide_Oscillator. html

nlf2

Second order normalized digital waveguide resonator.

Usage

```
_ : nlf2(f,r) : _
```

Where:

- f: resonance frequency (Hz)
- r: loss factor for exponential decay (set to 1 to make a sinusoidal oscillator)

Reference

 $https://ccrma.stanford.edu/\sim jos/pasp/Power_Normalized_Waveguide_Filters.html$

apnl

Passive Nonlinear Allpass based on Pierce switching springs idea. Switch between allpass coefficient a1 and a2 at signal zero crossings.

```
_ : apnl(a1,a2) : _
```

Where:

• a1 and a2: allpass coefficients

Reference

• "A Passive Nonlinear Digital Filter Design ..." by John R. Pierce and Scott A. Van Duyne, JASA, vol. 101, no. 2, pp. 1120-1126, 1997

Ladder/Lattice Allpass Filters

An allpass filter has gain 1 at every frequency, but variable phase. Ladder/lattice allpass filters are specified by reflection coefficients. They are defined here as nested allpass filters, hence the names allpassn*.

References

- https://ccrma.stanford.edu/~jos/pasp/Nested_Allpass_Filters.html
- Linear Prediction of Speech, Markel and Gray, Springer Verlag, 1976

allpassn

Two-multiply lattice - each section is two multiply-adds.

Usage:

```
_ : allpassn(n,sv) : _
```

Where:

- n: the order of the filter
- sv: the reflexion coefficients (-1 1)

References

• J. O. Smith and R. Michon, "Nonlinear Allpass Ladder Filters in FAUST", in Proceedings of the 14th International Conference on Digital Audio Effects (DAFx-11), Paris, France, September 19-23, 2011.

allpassnn

Normalized form - four multiplies and two adds per section, but coefficients can be time varying and nonlinear without "parametric amplification" (modulation of signal energy).

Usage:

```
_ : allpassnn(n,tv) : _
Where:
• n: the order of the filter
• tv: the reflexion coefficients (-PI PI)
```

allpasskl

Kelly-Lochbaum form - four multiplies and two adds per section, but all signals have an immediate physical interpretation as traveling pressure waves, etc.

Usage:

```
= : allpassnkl(n,sv) : _
Where:
• n: the order of the filter
• sv: the reflexion coefficients (-1 1)
```

allpass1m

One-multiply form - one multiply and three adds per section. Normally the most efficient in special-purpose hardware.

_ : allpassn1m(n,sv) : _

Where:

- n: the order of the filter
- sv: the reflexion coefficients (-1 1)

Digital Filter Sections Specified as Analog Filter Sections

tf2s and tf2snp

Second-order direct-form digital filter, specified by ANALOG transfer-function polynomials B(s)/A(s), and a frequency-scaling parameter. Digitization via the bilinear transform is built in.

Usage

_ : tf2s(b2,b1,b0,a1,a0,w1) : _

Where:

and w1 is the desired digital frequency (in radians/second) corresponding to analog frequency 1 rad/sec (i.e., s=j).

Example

A second-order ANALOG Butterworth lowpass filter, normalized to have cutoff frequency at 1 rad/sec, has transfer function

where a1 = sqrt(2). Therefore, a DIGITAL Butterworth lowpass cutting off at SR/4 is specified as tf2s(0,0,1,sqrt(2),1,PI*SR/2);

Method

Bilinear transform scaled for exact mapping of w1.

Reference

 $https://ccrma.stanford.edu/\sim jos/pasp/Bilinear_Transformation.html$

tf3s1f

Analogous to tf2s above, but third order, and using the typical low-frequency-matching bilinear-transform constant 2/T ("lf" series) instead of the specific-frequency-matching value used in tf2s and tf1s. Note the lack of a "w1" argument.

Usage

```
_ : tf3slf(b3,b2,b1,b0,a3,a2,a1,a0) : _
```

tf1s

First-order direct-form digital filter, specified by ANALOG transfer-function polynomials B(s)/A(s), and a frequency-scaling parameter.

Usage

tf1s(b1,b0,a0,w1)

Where:

$$b1 s + b0$$

$$H(s) = ----s + a0$$

and w1 is the desired digital frequency (in radians/second) corresponding to analog frequency 1 rad/sec (i.e., s = j).

Example

A first-order ANALOG Butterworth lowpass filter, normalized to have cutoff frequency at 1 rad/sec, has transfer function

$$1$$
 $H(s) = ---- s + 1$

so b0=a0=1 and b1=0. Therefore, a DIGITAL first-order Butterworth lowpass with gain -3dB at SR/4 is specified as

tf1s(0,1,1,PI*SR/2); // digital half-band order 1 Butterworth

Method

Bilinear transform scaled for exact mapping of w1.

Reference

 $https://ccrma.stanford.edu/{\sim}jos/pasp/Bilinear_Transformation.html$

tf2sb

Bandpass mapping of tf2s: In addition to a frequency-scaling parameter w1 (set to HALF the desired passband width in rad/sec), there is a desired center-frequency parameter wc (also in rad/s). Thus, tf2sb implements a fourth-order digital bandpass filter section specified by the coefficients of a second-order analog lowpass prototpe section. Such sections can be combined in series for higher orders. The order of mappings is (1) frequency scaling (to set lowpass cutoff w1), (2) bandpass mapping to wc, then (3) the bilinear transform, with the usual scale parameter 2*SR. Algebra carried out in maxima and pasted here.

Usage

```
_ : tf2sb(b2,b1,b0,a1,a0,w1,wc) : _
```

tf1sb

First-to-second-order lowpass-to-bandpass section mapping, analogous to tf2sb above.

Usage

```
_ : tf1sb(b1,b0,a0,w1,wc) : _
```

Simple Resonator Filters

resonlp

Simple resonant lowpass filter based on tf2s (virtual analog). resonlp is a standard Faust function.

Usage

```
_ : resonlp(fc,Q,gain) : _
_ : resonhp(fc,Q,gain) : _
_ : resonbp(fc,Q,gain) : _
```

Where:

- fc: center frequency (Hz)
- Q: q
- gain: gain (0-1)

resonhp

Simple resonant highpass filters based on tf2s (virtual analog). resonhp is a standard Faust function.

Usage

```
_ : resonlp(fc,Q,gain) : _
_ : resonhp(fc,Q,gain) : _
_ : resonbp(fc,Q,gain) : _
```

Where:

- fc: center frequency (Hz)
- Q: q
- gain: gain (0-1)

resonbp

Simple resonant bandpass filters based on tf2s (virtual analog). resonbp is a standard Faust function.

Usage

```
_ : resonlp(fc,Q,gain) : _
_ : resonhp(fc,Q,gain) : _
_ : resonbp(fc,Q,gain) : _
```

- fc: center frequency (Hz)
- Q: q

• gain: gain (0-1)

Butterworth Lowpass/Highpass Filters

lowpass

Nth-order Butterworth lowpass filter. lowpass is a standard Faust function.

Usage

```
_ : lowpass(N,fc) : _
```

Where:

- N: filter order (number of poles) [nonnegative constant integer]
- fc: desired cut-off frequency (-3dB frequency) in Hz

References

- https://ccrma.stanford.edu/~jos/filters/Butterworth_Lowpass_Design.html
- butter function in Octave ("[z,p,g] = butter(N,1,'s');")

highpass

Nth-order Butterworth highpass filters. highpass is a standard Faust function.

Usage

```
_ : highpass(N,fc) : _
```

Where:

- N: filter order (number of poles) [nonnegative constant integer]
- fc: desired cut-off frequency (-3dB frequency) in Hz

References

- https://ccrma.stanford.edu/~jos/filters/Butterworth_Lowpass_Design.html
- butter function in Octave ("[z,p,g] = butter(N,1,'s');")

lowpass0_highpass1 TODO

Special Filter-Bank Delay-Equalizing Allpass Filters

These special allpass filters are needed by filterbank et al. below. They are equivalent to (lowpass(N,fc) + | - highpass(N,fc))/2, but with canceling polezero pairs removed (which occurs for odd N).

lowpass_plus|minus_highpass TODO

Elliptic (Cauer) Lowpass Filters

Elliptic (Cauer) Lowpass Filters

References

- $\bullet \quad < http://en.wikipedia.org/wiki/Elliptic_filter$
- $\bullet\,$ functions neauer and ellip in Octave

lowpass3e

Third-order Elliptic (Cauer) lowpass filter.

Usage

```
_ : lowpass3e(fc) : _
```

Where:

• fc: -3dB frequency in Hz

Design

For spectral band-slice level display (see octave_analyzer3e):

```
[z,p,g] = ncauer(Rp,Rs,3); % analog zeros, poles, and gain, where Rp = 60 % dB ripple in stopband Rs = 0.2 % dB ripple in passband
```

lowpass6e

Sixth-order Elliptic/Cauer lowpass filter.

Usage

```
_ : lowpass6e(fc) : _
```

Where:

• fc: -3dB frequency in Hz

Design

For spectral band-slice level display (see octave_analyzer6e):

```
[z,p,g] = ncauer(Rp,Rs,6); % analog zeros, poles, and gain, where Rp = 80 % dB ripple in stopband Rs = 0.2 % dB ripple in passband
```

Elliptic Highpass Filters

highpass3e

Third-order Elliptic (Cauer) highpass filter. Inversion of lowpass3e wrt unit circle in s plane (s <- 1/s)

Usage

```
_ : highpass3e(fc) : _
```

Where:

• fc: -3dB frequency in Hz

highpass6e

Sixth-order Elliptic/Cauer highpass filter. Inversion of lowpass3e wrt unit circle in s plane (s <- 1/s)

Usage

```
_ : highpass6e(fc) : _
```

Where:

• fc: -3dB frequency in Hz

Butterworth Bandpass/Bandstop Filters

bandpass

Order 2*Nh Butterworth bandpass filter made using the transformation s <- s + wc^2/s on lowpass(Nh), where wc is the desired bandpass center frequency. The lowpass(Nh) cutoff w1 is half the desired bandpass width. bandpass is a standard Faust function.

Usage

```
_ : bandpass(Nh,fl,fu) : _
```

Where:

- Nh: HALF the desired bandpass order (which is therefore even)
- fl: lower -3dB frequency in Hz
- fu: upper -3dB frequency in Hz Thus, the passband width is fu-f1, and its center frequency is (f1+fu)/2.

Reference

http://cnx.org/content/m16913/latest/

bandstop

Order 2*Nh Butterworth bandstop filter made using the transformation s <- s + wc^2/s on highpass(Nh), where wc is the desired bandpass center frequency. The highpass(Nh) cutoff w1 is half the desired bandpass width. bandstop is a standard Faust function.

Usage

_ : bandstop(Nh,fl,fu) : _

Where:

- Nh: HALF the desired bandstop order (which is therefore even)
- fl: lower -3dB frequency in Hz
- fu: upper -3dB frequency in Hz Thus, the passband (stopband) width is fu-fl, and its center frequency is (fl+fu)/2.

Reference

http://cnx.org/content/m16913/latest/

Elliptic Bandpass Filters

bandpass6e

Order 12 elliptic bandpass filter analogous to bandpass (6).

bandpass12e

Order 24 elliptic bandpass filter analogous to bandpass (6).

Parametric Equalizers (Shelf, Peaking)

Parametric Equalizers (Shelf, Peaking)

References

- http://en.wikipedia.org/wiki/Equalization
- http://www.musicdsp.org/files/Audio-EQ-Cookbook.txt
- Digital Audio Signal Processing, Udo Zolzer, Wiley, 1999, p. 124
- $\bullet \ \ https://ccrma.stanford.edu/\sim jos/filters/Low_High_Shelving_Filters.html>$
- https://ccrma.stanford.edu/~jos/filters/Peaking Equalizers.html>
- maxmsp.lib in the Faust distribution
- bandfilter.dsp in the faust2pd distribution

low_shelf

First-order "low shelf" filter (gain boost|cut between dc and some frequency) low_shelf is a standard Faust function.

Usage

```
_ : lowshelf(N,L0,fx) : _
_ : low_shelf(L0,fx) : _ // default case (order 3)
_ : lowshelf_other_freq(N,L0,fx) : _
```

Where: * N: filter order 1, 3, 5, ... (odd only). (default should be 3) * L0: desired level (dB) between dc and fx (boost L0>0 or cut L0<0) * fx: -3dB frequency of lowpass band (L0>0) or upper band (L0<0) (see "SHELF SHAPE" below).

The gain at SR/2 is constrained to be 1. The generalization to arbitrary odd orders is based on the well known fact that odd-order Butterworth band-splits are all pass-complementary (see filterbank documentation below for references).

Shelf Shape

The magnitude frequency response is approximately piecewise-linear on a log-log plot ("BODE PLOT"). The Bode "stick diagram" approximation L(lf) is easy to state in dB versus dB-frequency lf = dB(f):

- L0 > 0:
- L(lf) = L0, f between 0 and fx = 1st corner frequency;
- L(lf) = L0 N * (lf lfx), f between fx and f2 = 2nd corner frequency;
- L(lf) = 0, lf > lf2.
- lf2 = lfx + L0/N = dB-frequency at which level gets back to 0 dB.
- L0 < 0:
- L(lf) = L0, f between 0 and f1 = 1st corner frequency;
- L(lf) = N * (lfx lf), f between f1 and lfx = 2nd corner frequency;
- L(lf) = 0, lf > lfx.
- lf1 = lfx + L0/N = dB-frequency at which level goes up from L0.

See lowshelf_other_freq.

high_shelf

First-order "high shelf" filter (gain boost|cut above some frequency). high_shelf is a standard Faust function.

Usage

```
_ : highshelf(N,Lpi,fx) : _
_ : high_shelf(L0,fx) : _ // default case (order 3)
_ : highshelf_other_freq(N,Lpi,fx) : _
```

Where:

- N: filter order 1, 3, 5, ... (odd only).
- Lpi: desired level (dB) between fx and SR/2 (boost Lpi>0 or cut Lpi<0)
- fx: -3dB frequency of highpass band (L0>0) or lower band (L0<0) (Use highshelf_other_freq() below to find the other one.)

The gain at dc is constrained to be 1. See lowshelf documentation above for more details on shelf shape.

peak_eq

Second order "peaking equalizer" section (gain boost or cut near some frequency) Also called a "parametric equalizer" section. peak_eq is a standard Faust function.

Usage

```
_ : peak_eq(Lfx,fx,B) : _;
```

Where:

- Lfx: level (dB) at fx (boost Lfx>0 or cut Lfx<0)
- fx: peak frequency (Hz)
- B: bandwidth (B) of peak in Hz

peak_eq_cq

Constant-Q second order peaking equalizer section.

Usage

```
_ : peak_eq_cq(Lfx,fx,Q) : _;
```

- Lfx: level (dB) at fx
- fx: boost or cut frequency (Hz)
- Q: "Quality factor" = fx/B where B = bandwidth of peak in Hz

Regalia-Mitra second order peaking equalizer section

Usage

peak_eq_rm

```
_ : peak_eq_rm(Lfx,fx,tanPiBT) : _;
```

Where:

- Lfx: level (dB) at fx
- fx: boost or cut frequency (Hz)
- tanPiBT: tan(PI*B/SR), where B = -3dB bandwidth (Hz) when $10^{(Lfx/20)} = 0 \sim PI*B/SR$ for narrow bandwidths B

Reference

P.A. Regalia, S.K. Mitra, and P.P. Vaidyanathan, "The Digital All-Pass Filter: A Versatile Signal Processing Building Block" Proceedings of the IEEE, 76(1):19-37, Jan. 1988. (See pp. 29-30.)

spectral_tilt

Spectral tilt filter, providing an arbitrary spectral rolloff factor alpha in (-1,1), where -1 corresponds to one pole (-6 dB per octave), and +1 corresponds to one zero (+6 dB per octave). In other words, alpha is the slope of the ln magnitude versus ln frequency. For a "pinking filter" (e.g., to generate 1/f noise from white noise), set alpha to -1/2.

Usage

```
_ : spectral_tilt(N,f0,bw,alpha) : _
```

- N: desired integer filter order (fixed at compile time)
- f0: lower frequency limit for desired roll-off band
- bw: bandwidth of desired roll-off band
- alpha: slope of roll-off desired in nepers per neper (ln mag / ln radian freq)

Examples

See $spectral_tilt_demo$.

Reference

Link to appear here when write up is done

levelfilter

Dynamic level lowpass filter. levelfilter is a standard Faust function.

Usage

```
_ : levelfilter(L,freq) : _
```

Where:

- L: desired level (in dB) at Nyquist limit (SR/2), e.g., -60
- freq: corner frequency (-3dB point) usually set to fundamental freq
- N: Number of filters in series where L = L/N

Reference

https://ccrma.stanford.edu/realsimple/faust_strings/Dynamic_Level_Lowpass_Filter.html

levelfilterN

Dynamic level lowpass filter.

Usage

```
_ : levelfilterN(N,freq,L) : _
```

- L: desired level (in dB) at Nyquist limit (SR/2), e.g., -60
- freq: corner frequency (-3dB point) usually set to fundamental freq
- N: Number of filters in series where L = L/N

Reference

 $https://ccrma.stanford.edu/realsimple/faust_strings/Dynamic_Level_Lowpass_Filter.html$

Mth-Octave Filter-Banks

Mth-octave filter-banks split the input signal into a bank of parallel signals, one for each spectral band. They are related to the Mth-Octave Spectrum-Analyzers in analysis.lib. The documentation of this library contains more details about the implementation. The parameters are:

- M: number of band-slices per octave (>1)
- N: total number of bands (>2)
- ftop: upper bandlimit of the Mth-octave bands (<SR/2)

In addition to the Mth-octave output signals, there is a highpass signal containing frequencies from ftop to SR/2, and a "dc band" lowpass signal containing frequencies from 0 (dc) up to the start of the Mth-octave bands. Thus, the N output signals are

highpass(ftop), MthOctaveBands(M,N-2,ftop), dcBand(ftop*2^(-M*(N-1)))

A Filter-Bank is defined here as a signal bandsplitter having the property that summing its output signals gives an allpass-filtered version of the filter-bank input signal. A more conventional term for this is an "allpass-complementary filter bank". If the allpass filter is a pure delay (and possible scaling), the filter bank is said to be a "perfect-reconstruction filter bank" (see Vaidyanathan-1993 cited below for details). A "graphic equalizer", in which band signals are scaled by gains and summed, should be based on a filter bank.

The filter-banks below are implemented as Butterworth or Elliptic spectrumanalyzers followed by delay equalizers that make them allpass-complementary.

Increasing Channel Isolation

Go to higher filter orders - see Regalia et al. or Vaidyanathan (cited below) regarding the construction of more aggressive recursive filter-banks using elliptic or Chebyshev prototype filters.

References

• "Tree-structured complementary filter banks using all-pass sections", Regalia et al., IEEE Trans. Circuits & Systems, CAS-34:1470-1484, Dec. 1987

- "Multirate Systems and Filter Banks", P. Vaidyanathan, Prentice-Hall, 1993
- Elementary filter theory: https://ccrma.stanford.edu/~jos/filters/

mth_octave_filterbank[n]

Allpass-complementary filter banks based on Butterworth band-splitting. For Butterworth band-splits, the needed delay equalizer is easily found.

Usage

```
_: mth_octave_filterbank(0,M,ftop,N) : par(i,N,_); // Oth-order
_: mth_octave_filterbank_alt(0,M,ftop,N) : par(i,N,_); // dc-inverted version
Also for convenience:
_: mth_octave_filterbank3(M,ftop,N) : par(i,N,_); // 3d-order Butterworth
_: mth_octave_filterbank5(M,ftop,N) : par(i,N,_); // 5th-roder Butterworth
mth_octave_filterbank_default = mth_octave_analyzer6e;
```

Where:

- 0: order of filter used to split each frequency band into two
- M: number of band-slices per octave
- ftop: highest band-split crossover frequency (e.g., 20 kHz)
- N: total number of bands (including dc and Nyquist)

Arbritary-Crossover Filter-Banks and Spectrum Analyzers

These are similar to the Mth-octave analyzers above, except that the band-split frequencies are passed explicitly as arguments.

filterbank

Filter bank. filterbank is a standard Faust function.

Usage

```
_ : filterbank (0,freqs) : par(i,N,_); // Butterworth band-splits Where:
```

- 0: band-split filter order (ODD integer required for filterbank[i])
- freqs: (fc1,fc2,...,fcNs) [in numerically ascending order], where Ns=N-1 is the number of octave band-splits (total number of bands N=Ns+1).

If frequencies are listed explicitly as arguments, enclose them in parens:

```
_ : filterbank(3,(fc1,fc2)) : _,_,_
```

filterbanki

Inverted-dc filter bank.

Usage

```
_ : filterbanki(0,freqs) : par(i,N,_); // Inverted-dc version
```

- Where:
 - 0: band-split filter order (ODD integer required for filterbank[i])
 - freqs: (fc1,fc2,...,fcNs) [in numerically ascending order], where Ns=N-1 is the number of octave band-splits (total number of bands N=Ns+1).

If frequencies are listed explicitly as arguments, enclose them in parens:

```
_ : filterbanki(3,(fc1,fc2)) : _,_,_
```

hoa.lib

Faust library for high order ambisonic.

It should be used using the ho environment:

```
ho = library("ho.lib");
process = ho.functionCall;
```

Another option is to import stdfaust.lib which already contains the ho environment:

```
import("stdfaust.lib");
process = ho.functionCall;
```

encoder

Ambisonic encoder. Encodes a signal in the circular harmonics domain depending on an order of decomposition and an angle.

Usage

encoder(n, x, a) : _

Where:

- n: the orderx: the signal
- a: the angle

decoder

Decodes an ambisonics sound field for a circular array of loudspeakers.

Usage

_ : decoder(n, p) : _

Where:

- n: the order
- p: the number of speakers

Note

Number of loudspeakers must be greater or equal to 2n+1. It's preferable to use 2n+2 loudspeakers.

decoderStereo

Decodes an ambisonic sound field for stereophonic configuration. An "home made" ambisonic decoder for stereophonic restitution $(30^{\circ} - 330^{\circ})$: Sound field lose energy around 180° . You should use <code>inPhase</code> optimization with ponctual sources. #### Usage

_ : decoderStereo(n) : _

Where:

• n: the order

Optimization Functions

Functions to weight the circular harmonics signals depending to the ambisonics optimization. It can be basic for no optimization, maxRe or inPhase.

optimBasic

The basic optimization has no effect and should be used for a perfect circle of loudspeakers with one listener at the perfect center loudspeakers array.

optimMaxRe

The maxRe optimization optimize energy vector. It should be used for an auditory confined in the center of the loudspeakers array.

Usage

```
_ : optimMaxRe(n) : _
Where:
• n: the order
```

optimInPhase

The inPhase Optimization optimize energy vector and put all loudspeakers signals n phase. It should be used for an auditory.

Usage

```
" optimInPhase(n) : \_" here: n: the order
```

wider

Can be used to wide the diffusion of a localized sound. The order depending signals are weighted and appear in a logarithmic way to have linear changes.

Usage

```
_ : wider(n,w) : _
```

Where:

- n: the order
- w: the width value between 0-1

map

It simulate the distance of the source by applying a gain on the signal and a wider processing on the soundfield.

Usage

```
map(n, x, r, a)
```

Where:

- n: the order
- x: the signal
- \mathbf{r} : the radius
- $\bullet\,$ a: the angle in radian

rotate

Rotates the sound field.

Usage

```
_ : rotate(n, a) : _
```

Where:

• n: the order

• a: the angle in radian

math.lib

Mathematic library for Faust. Some functions are implemented as Faust foreign functions of math.h functions that are not part of Faust's primitives. Defines also various constants and several utilities.

It should be used using the fi environment:

```
ma = library("math.lib");
process = ma.functionCall;
```

Another option is to import stdfaust.lib which already contains the ma environment:

```
import("stdfaust.lib");
process = ma.functionCall;
```

Functions Reference

SR

Current sampling rate (between 1Hz and 192000Hz). Constant during program execution.

Usage SR: _ BS Current block-size. Can change during the execution. Usage BS: _

PI
Constant PI in double precisio.n
Usage
PI : _
FTZ
Flush to zero: force samples under the "maximum subnormal number" to be zero. Usually not needed in C++ because the architecture file take care of this, but can be useful in javascript for instance.
Usage
_ : ftz : _
See : $http://docs.oracle.com/cd/E19957-01/806-3568/ncg_math.html$
neg
Invert the sign (-x) of a signal.
Usage
_ : neg : _
sub(x,y)
Subtract x and y.

Compute the inverse (1/x) of the input signal.

inv

_ : inv : _
cbrt
Computes the cube root of the input signal.
Usage
_ : cbrt : _
hypot
Computes the euclidian distance of the two input signals $\operatorname{sqrt}(\mathbf{x}x+y\mathbf{y})$ without undue overflow or underflow.
Usage
, : hypot : _
ldexp
Takes two input signals: x and n , and multiplies x by 2 to the power n .
Usage
, : ldexp : _
scalb
Takes two input signals: x and n , and multiplies x by 2 to the power n .
Usage
, : scalb : _

Usage

log	1p
-----	----

Computes log(1 + x) without undue loss of accuracy when x is nearly zero.

Usage

```
_ : log1p : _
```

logb

Return exponent of the input signal as a floating-point number.

Usage

```
_ : logb : _ _____
```

ilogb

Return exponent of the input signal as an integer number.

Usage

log2

Returns the base 2 logarithm of x.

Usage

```
_ : log2 : _
```

expm1

Return exponent of the input signal minus 1 with better precision.

Usage
_ : expm1 : _
acosh
Computes the principle value of the inverse hyperbolic cosine of the input signal.
Usage
_ : acosh : _
asinh
Computes the inverse hyperbolic sine of the input signal.
Usage
_ : asinh : _
atanh
Computes the inverse hyperbolic tangent of the input signal.
Usage
_ : atanh : _
sinh
Computes the hyperbolic sine of the input signal.
Usage
_ : sinh : _
_ · billi · _

Computes the hyperbolic cosine of the input signal.
Usage
_ : cosh : _
tanh
Computes the hyperbolic tangent of the input signal.
Usage
_ : tanh : _
erf
Computes the error function of the input signal.
Usage
_ : erf : _
·
erfc
Computes the complementary error function of the input signal
Usage
_ : erfc : _
gamma

cosh

Computes the gamma function of the input signal.

Usage
_ : gamma : _

lgamma
Calculates the natural logorithm of the absolute value of the gamma function of the input signal.
Usage
_ : lgamma : _
JO
Computes the Bessel function of the first kind of order 0 of the input signal.
**
Usage _ : J0 : _
J1
Computes the Bessel function of the first kind of order 1 of the input signal.
Usage
_ : J1 : _
т
Jn

Computes the Bessel function of the first kind of order n (first input signal) of

the second input signal.

Usage
, : Jn : _
YO
Computes the linearly independent Bessel function of the second kind of order 0 of the input signal.
Usage
_ : YO : _
Y1
Computes the linearly independent Bessel function of the second kind of order 1 of the input signal.
Usage
_ : YO : _

Yn
Computes the linearly independent Bessel function of the second kind of order n (first input signal) of the second input signal.
Usage
, : Yn : _
fabs, fmax, fmin

Just for compatibility...

```
fabs = abs
fmax = max
fmin = min
np2
Gives the next power of 2 of x.
Usage
np2(n) : _
Where:
   • n: an integer
frac
Gives the fractional part of n.
Usage
frac(n) : _
Where:
   • n: a decimal number
isnan
Return non-zero if and only if x is a NaN.
Usage
isnan(x)
_ : isnan : _
Where:
   \bullet\, x: signal to analyse
```

chebychev

Chebychev transformation of order n.

Usage

```
_{-} : chebychev(n) : _{-}
```

Where:

 $\bullet\,$ n: the order of the polynomial

Semantics

```
T[0](x) = 1,

T[1](x) = x,

T[n](x) = 2x*T[n-1](x) - T[n-2](x)
```

Reference

http://en.wikipedia.org/wiki/Chebyshev_polynomial

chebychevpoly

Linear combination of the first Chebyshev polynomials.

Usage

```
_ : chebychevpoly((c0,c1,...,cn)) : _
```

Where:

• cn: the different Chebychevs polynomials such that: chebychevpoly($(c0,c1,\ldots,cn)$) = Sum of chebychev(i)*ci

Reference

http://www.csounds.com/manual/html/chebyshevpoly.html

diffn

Negated first-roder difference.

Usage

```
_ : diffn : _
```

misceffect.lib

This library contains a collection of audio effects.

It should be used using the ef environment:

```
ef = library("misceffect.lib");
process = ef.functionCall;
```

Another option is to import stdfaust.lib which already contains the ef environment:

```
import("stdfaust.lib");
process = ef.functionCall;
```

Dynamic

cubicnl

Cubic nonlinearity distortion. cubicnl is a standard Faust library.

Usage:

```
_ : cubicnl(drive,offset) : _
_ : cubicnl_nodc(drive,offset) : _
```

Where:

- drive: distortion amount, between 0 and 1
- offset: constant added before nonlinearity to give even harmonics. Note: offset can introduce a nonzero mean feed cubicnl output to dcblocker to remove this.

References:

- $\bullet \ \, \rm https://ccrma.stanford.edu/\sim jos/pasp/Cubic_Soft_Clipper.html$
- $\bullet \ \ https://ccrma.stanford.edu/\sim jos/pasp/Nonlinear_Distortion.html$

gate_mono

Mono signal gate. gate_mono is a standard Faust function.

Usage

```
_ : gate_mono(thresh,att,hold,rel) : _
```

Where:

- thresh: dB level threshold above which gate opens (e.g., -60 dB)
- att: attack time = time constant (sec) for gate to open (e.g., 0.0001 s = 0.1 ms)
- hold: hold time = time (sec) gate stays open after signal level < thresh (e.g., 0.1 s)
- rel: release time = time constant (sec) for gate to close (e.g., 0.020 s = 20 ms)

References

- http://en.wikipedia.org/wiki/Noise_gate
- $\bullet \ \ http://www.soundonsound.com/sos/apr01/articles/advanced.asp$
- http://en.wikipedia.org/wiki/Gating_(sound_engineering)

gate_stereo

Stereo signal gates. gate_stereo is a standard Faust function.

Usage

```
_,_ : gate_stereo(thresh,att,hold,rel) : _,_
```

- thresh: dB level threshold above which gate opens (e.g., -60 dB)
- att: attack time = time constant (sec) for gate to open (e.g., 0.0001 s = 0.1 ms)
- hold: hold time = time (sec) gate stays open after signal level < thresh (e.g., $0.1~\mathrm{s}$)
- rel: release time = time constant (sec) for gate to close (e.g., 0.020 s = 20 ms)

References

- http://en.wikipedia.org/wiki/Noise_gate
- http://www.soundonsound.com/sos/apr01/articles/advanced.asp
- http://en.wikipedia.org/wiki/Gating_(sound_engineering)

Filtering

speakerbp

Dirt-simple speaker simulator (overall bandpass eq with observed roll-offs above and below the passband).

Low-frequency speaker model = +12 dB/octave slope breaking to flat near f1. Implemented using two dc blockers in series.

High-frequency model = -24 dB/octave slope implemented using a fourth-order Butterworth lowpass.

Example based on measured Celestion G12 (12" speaker):

speakerbp is a standard Faust function

Usage

```
speakerbp(f1,f2)
_ : speakerbp(130,5000) : _
```

piano_dispersion_filter

Piano dispersion allpass filter in closed form.

Usage

```
piano_dispersion_filter(M,B,f0)
_ : piano_dispersion_filter(1,B,f0) : +(totalDelay),_ : fdelay(maxDelay) : _
Where:
```

- M: number of first-order allpass sections (compile-time only) Keep below 20. 8 is typical for medium-sized piano strings.
- B: string inharmonicity coefficient (0.0001 is typical)
- f0: fundamental frequency in Hz

Outputs

- MINUS the estimated delay at f0 of all pass chain in samples, provided in negative form to facilitate subtraction from delay-line length.
- Output signal from allpass chain

stereo_width

Stereo Width effect using the Blumlein Shuffler technique. stereo_width is a standard Faust function.

Usage

```
\_,\_ : stereo_width(w) : \_,\_
```

Where:

• w: stereo width between 0 and 1

At w=0, the output signal is mono ((left+right)/2 in both channels). At w=1, there is no effect (original stereo image). Thus, w between 0 and 1 varies stereo width from 0 to "original".

Reference

• "Applications of Blumlein Shuffling to Stereo Microphone Techniques" Michael A. Gerzon, JAES vol. 42, no. 6, June 1994

Time Based

echo

A simple echo effect.

echo is a standard Faust function

Usage

```
_ : echo(maxDuration,duration,feedback) : _
```

- maxDuration: the max echo duration in seconds
- duration: the echo duration in seconds
- feedback: the feedback coefficient

Pitch Shifting

transpose

A simple pitch shifter based on 2 delay lines. transpose is a standard Faust function.

Usage

```
_ : transpose(w, x, s) : _
```

Where:

- w: the window length (samples)
- x: crossfade duration duration (samples)
- s: shift (semitones)

Meshes

mesh_square

Square Rectangular Digital Waveguide Mesh.

Usage

```
bus(4*N) : mesh\_square(N) : bus(4*N);
```

Where:

• N: number of nodes along each edge - a power of two (1,2,4,8,...)

Reference

 $https://ccrma.stanford.edu/\sim jos/pasp/Digital_Waveguide_Mesh.html$

Signal Order In and Out

The mesh is constructed recursively using 2x2 embeddings. Thus, the top level of mesh_square(M) is a block 2x2 mesh, where each block is a mesh(M/2). Let these blocks be numbered 1,2,3,4 in the geometry NW,NE,SW,SE, i.e., as 1 2 3 4 Each block has four vector inputs and four vector outputs, where the length of each vector is M/2. Label the input vectors as Ni,Ei,Wi,Si, i.e., as the inputs

from the North, East South, and West, and similarly for the outputs. Then, for example, the upper left input block of M/2 signals is labeled 1Ni. Most of the connections are internal, such as 1Eo -> 2Wi. The 8*(M/2) input signals are grouped in the order 1Ni 2Ni 3Si 4Si 1Wi 3Wi 2Ei 4Ei and the output signals are 1No 1Wo 2No 2Eo 3So 3Wo 4So 4Eo or

In: 1No 1Wo 2No 2Eo 3So 3Wo 4So 4Eo

Out: 1Ni 2Ni 3Si 4Si 1Wi 3Wi 2Ei 4Ei

Thus, the inputs are grouped by direction N,S,W,E, while the outputs are grouped by block number 1,2,3,4, which can also be interpreted as directions NW, NE, SW, SE. A simple program illustrating these orderings is process = mesh_square(2);

Example

Reflectively terminated mesh impulsed at one corner:

```
mesh_square_test(N,x) = mesh_square(N)~(busi(4*N,x)) // input to corner with { busi(N,x) = bus(N) : par(i,N,*(-1)) : par(i,N-1,_), +(x); }; process = 1-1' : mesh_square_test(4); // all modes excited forever
```

In this simple example, the mesh edges are connected as follows:

```
1No -> 1Ni, 1Wo -> 2Ni, 2No -> 3Si, 2Eo -> 4Si, 3So -> 1Wi, 3Wo -> 3Wi, 4So -> 2Ei, 4Eo -> 4Ei
```

A routing matrix can be used to obtain other connection geometries.

miscoscillator.lib

This library contains a collection of sound generators.

It should be used using the os environment:

```
os = library("miscoscillator.lib");
process = os.functionCall;
```

Another option is to import stdfaust.lib which already contains the os environment:

```
import("stdfaust.lib");
process = os.functionCall;
```

Wave-Table-Based Oscillators

sinwaveform

Sine waveform ready to use with a rdtable.

Usage

sinwaveform(tablesize) : _

Where:

• tablesize: the table size

coswaveform

Cosine waveform ready to use with a rdtable.

Usage

coswaveform(tablesize) : _

Where:

• tablesize: the table size

phasor

A simple phasor to be used with a rdtable. phasor is a standard Faust function.

Usage

phasor(tablesize,freq) : _

Where:

- tablesize: the table size
- $\bullet\,$ freq: the frequency of the wave (Hz)

oscsin

Sine wave oscillator. oscsin is a standard Faust function.

Usage
oscsin(freq) : _
Where:
• freq: the frequency of the wave (Hz)
OSCOS
Cosine wave oscillator.
Usage
osccos(freq) : _
Where:
• freq: the frequency of the wave (Hz)
oscp
A sine wave generator with controllable phase.
Usage
oscp(freq,p) : _
Where:
freq: the frequency of the wave (Hz)p: the phase in radian

osci

Interpolated phase sine wave oscillator.

Usage osci(freq) : _ Where: freq: the frequency of the wave (Hz)

LFOs

Low-frequency oscillators have prefix lf_{-} (no aliasing suppression, signal-means not necessarily zero).

lf_imptrain

Unit-amplitude low-frequency impulse train. lf_imptrain is a standard Faust function.

Usage

```
lf_imptrain(freq) : _
Where:
    freq: frequency in Hz
```

lf_pulsetrainpos

Unit-amplitude nonnegative LF pulse train, duty cycle between 0 and 1

Usage

```
lf_pulsetrainpos(freq,duty) : _
```

Where:

- freq: frequency in Hz
- duty: duty cycle between 0 and 1

lf_squarewavepos

Positive LF square wave in [0,1]

Usage
<pre>lf_squarewavepos(freq) : _</pre>
Where:
• freq: frequency in Hz
lf_squarewave
Zero-mean unit-amplitude LF square wave. ${\tt lf_squarewave}$ is a standard Faust function.
Usage
<pre>lf_squarewave(freq) : _</pre>
Where:
• freq: frequency in Hz
lf_trianglepos
Positive unit-amplitude LF positive triangle wave

lf_triangle

lf_trianglepos(freq) : _

• freq: frequency in Hz

Usage

Positive unit-amplitude LF triangle wave $\mbox{lf_triangle}$ is a standard Faust function.

Usage lf_triangle(freq) : _ Where: freq: frequency in Hz

Low Frequency Sawtooths

Sawtooth waveform oscillators for virtual analog synthesis et al. The 'simple' versions (lf_rawsaw, lf_sawpos and saw1), are mere samplings of the ideal continuous-time ("analog") waveforms. While simple, the aliasing due to sampling is quite audible. The differentiated polynomial waveform family (saw2, sawN, and derived functions) do some extra processing to suppress aliasing (not audible for very low fundamental frequencies). According to Lehtonen et al. (JASA 2012), the aliasing of saw2 should be inaudible at fundamental frequencies below 2 kHz or so, for a 44.1 kHz sampling rate and 60 dB SPL presentation level; fundamentals 415 and below required no aliasing suppression (i.e., saw1 is ok).

lf_rawsaw

Simple sawtooth waveform oscillator between 0 and period in samples.

Usage

lf_rawsaw(periodsamps)

Where:

 $\bullet\,$ periods amps: number of periods per samples

lf_sawpos

Simple sawtooth waveform oscillator between 0 and 1.

Usage

lf_sawpos(freq)

• freq: frequency
lf_saw
Simple sawtooth waveform. lf_saw is a standard Faust function.
Usage
lf_saw(freq)
Where:
• freq: frequency
lf_sawpos_phase
Simple sawtooth waveform oscillator between 0 and 1 with phase control.
Usage
lf_sawpos_phase(freq,phase)
Where:
freq: frequencyphase: phase

Bandlimited Sawtooth

Bandlimited Sawtooth

```
sawN(N,freq), sawNp, saw2dpw(freq), saw2(freq), saw3(freq), saw4(freq),
saw5(freq), saw6(freq), sawtooth(freq), saw2f2(freq) saw2f4(freq)
```

Method 1 (saw2)

Polynomial Transition Regions (PTR) (for aliasing suppression)

Reference

- Kleimola, J.; Valimaki, V., "Reducing Aliasing from Synthetic Audio Signals Using Polynomial Transition Regions," in Signal Processing Letters, IEEE, vol.19, no.2, pp.67-70, Feb. 2012
- https://aaltodoc.aalto.fi/bitstream/handle/123456789/7747/publication6. pdf?sequence=9
- http://research.spa.aalto.fi/publications/papers/spl-ptr/

Method 2 (sawN)

Differentiated Polynomial Waves (DPW) (for aliasing suppression)

Reference

"Alias-Suppressed Oscillators based on Differentiated Polynomial Waveforms", Vesa Valimaki, Juhan Nam, Julius Smith, and Jonathan Abel, IEEE Tr. Acoustics, Speech, and Language Processing (IEEE-ASLP), Vol. 18, no. 5, May 2010.

Other Cases

Correction-filtered versions of saw2: saw2f2, saw2f4 The correction filter compensates "droop" near half the sampling rate. See reference for sawN.

Usage

```
sawN(N,freq) : _
sawNp(N,freq,phase) : _
saw2dpw(freq) : _
saw2(freq) : _
saw3(freq) : _ // based on sawN
saw4(freq) : _ // based on sawN
saw5(freq) : _ // based on sawN
saw6(freq) : _ // based on sawN
sawtooth(freq) : _ // = saw2
saw2f2(freq) : _
saw2f4(freq) : _
```

- Where:
 - N: polynomial order
 - freq: frequency in Hz
 - phase: phase

SawN
TODO: implemented but not documented. For now, you can look at the source code.
\mathtt{sawNp}
TODO: implemented but not documented. For now, you can look at the source code.
saw2dpw
TODO: implemented but not documented. For now, you can look at the source code.
saw3
TODO: implemented but not documented. For now, you can look at the source code.
sawtooth
Alias-free sawtooth wave. 2nd order interpolation (based on saw2). sawtooth is a standard Faust function.
Usage
<pre>sawtooth(freq) : _</pre>
Where:
• freq: frequency

saw2f2

TODO: implemented but not documented. For now, you can look at the source code.

saw2f4

TODO: implemented but not documented. For now, you can look at the source code.

Bandlimited Pulse, Square, and Impulse Trains

Bandlimited Pulse, Square, and Impulse Trains

 $\verb"pulsetrain", \verb"pulsetrain", \verb"square", \verb"square", imptrain", imptrain", triangle, triangle \verb"N"$

All are zero-mean and meant to oscillate in the audio frequency range. Use simpler sample-rounded lf_* versions above for LFOs.

Usage

```
pulsetrainN(N,freq,duty) : _
pulsetrain(freq, duty) : _ // = pulsetrainN(2)
squareN(N, freq) : _
square : _ // = squareN(2)
imptrainN(N,freq) : _
imptrain : _ // = imptrainN(2)
triangleN(N,freq) : _
triangle : _ // = triangleN(2)
```

Where:

- N: polynomial order
- freq: frequency in Hz

pulsetrainN

TODO: implemented but not documented. For now, you can look at the source code.

113

pulsetrain

Bandlimited pulse train oscillator. Based on pulsetrainN(2). pulsetrain is a standard Faust function.

Usage

 $pulsetrain(freq, duty) : _$

Where:

- freq: frequency
- duty: duty cycle between 0 and 1

squareN

TODO: implemented but not documented. For now, you can look at the source code.

square

Bandlimited square wave oscillator. Based on squareN(2). square is a standard Faust function.

Usage

square(freq) : _

Where:

• freq: frequency

impulse

One-time impulse generated when the Faust process is started. impulse is a standard Faust function.

Usage
impulse : _
imptrainN
TODO: implemented but not documented. For now, you can look at the source code.
imptrain
Bandlimited impulse train generator. Based on ${\tt imptrainN(2)}$. ${\tt imptrain}$ is a standard Faust function.
Usage
<pre>imptrain(freq) : _</pre>
Where:
• freq: frequency
triangleN
TODO: implemented but not documented. For now, you can look at the source code.
triangle
Bandlimited triangle wave oscillator. Based on triangleN(2). triangle is a standard Faust function.
Usage
<pre>triangle(freq) : _</pre>
Where:
• freq: frequency

Filter-Based Oscillators

Filter-Based Oscillators

Usage

```
osc[b|r|rs|rc|s|w](f), where f = frequency in Hz.
```

References

- $\bullet \ \, \rm http://lac.linuxaudio.org/2012/download/lac12-slides-jos.pdf$
- $\bullet \ \ https://ccrma.stanford.edu/\sim jos/pdf/lac12-paper-jos.pdf$

oscb

Sinusoidal oscillator based on the biquad.

Usage

```
oscb(freq) : _
Where:
```

• freq: frequency

oscrq

Sinusoidal (sine and cosine) oscillator based on 2D vector rotation, = undamped "coupled-form" resonator = lossless 2nd-order normalized ladder filter.

Usage

```
oscrq(freq) : _,_
```

Where:

• freq: frequency

	re	

Reference
<u> </u>
oscrs
Sinusoidal (sine) oscillator based on 2D vector rotation, = undamped "coupled-form" resonator = lossless 2nd-order normalized ladder filter.
Usage
oscrs(freq) : _
Where:
• freq: frequency
Reference
• https://ccrma.stanford.edu/~jos/pasp/Normalized_Scattering_ Junctions.html
oscrc
Sinusoidal (cosine) oscillator based on 2D vector rotation, = undamped "coupled-form" resonator = lossless 2nd-order normalized ladder filter.
Usage
oscrc(freq) : _
Where:
• freq: frequency
Reference

osc

Default sine wave oscillator (same as oscrs). osc is a standard Faust function.

Usage

```
osc(freq) : _{-}
```

Where:

 $\bullet\,$ freq: the frequency of the wave (Hz)

oscs

Sinusoidal oscillator based on the state variable filter = undamped "modified-coupled-form" resonator = "magic circle" algorithm used in graphics

Waveguide-Resonator-Based Osccilators

Sinusoidal oscillator based on the waveguide resonator wgr.

oscw

Sinusoidal oscillator based on the waveguide resonator wgr. Unit-amplitude cosine oscillator.

Usage

```
oscwc(freq) : _
```

Where:

• freq: frequency

Reference

- https://ccrma.stanford.edu/~jos/pasp/Digital_Waveguide_Oscillator. html

os	C.	W	S
----	----	---	---

Sinusoidal oscillator based on the waveguide resonator wgr. Unit-amplitude sine oscillator

Usage

```
oscws(freq) : _{-}
```

Where:

• freq: frequency

Reference

- https://ccrma.stanford.edu/~jos/pasp/Digital_Waveguide_Oscillator. html

oscwq

Sinusoidal oscillator based on the waveguide resonator wgr. Unit-amplitude cosine and sine (quadrature) oscillator.

Usage

```
oscwq(freq) : _
```

Where:

• freq: frequency

Reference

- https://ccrma.stanford.edu/~jos/pasp/Digital_Waveguide_Oscillator. html

oscw

Sinusoidal oscillator based on the waveguide resonator wgr. Unit-amplitude cosine oscillator (default)

Functions Reference

import("stdfaust.lib");
process = no.functionCall;

noise

White noise generator (outputs random number between -1 and 1). Noise is a standard Faust function.

$\mathbf{U}\mathbf{sage}$	
noise : _	

multirandom

Generates multiple decorrelated random numbers in parallel.

Usage
<pre>multirandom(n) : _</pre>
Where:
• n: the number of decorrelated random numbers in parallel
multinoise
Generates multiple decorrelated noises in parallel.
Usage
<pre>multinoise(n) : _</pre>
Where:
• n: the number of decorrelated random numbers in parallel
noises
TODO.
pink_noise
Pink noise (1/f noise) generator (third-order approximation) ${\tt pink_noise}$ is a standard Faust function.
Usage
pink_noise : _;
<u> </u>
Reference:
$https://ccrma.stanford.edu/{\sim}jos/sasp/Example_Synthesis_1_F_Noise.html$

pink_noise_vm

Multi pink noise generator.

Usage

```
pink_noise_vm(N) : _;
```

Where:

• N: number of latched white-noise processes to sum, not to exceed size of (int) in C++ (typically 32).

References

- http://www.dsprelated.com/showarticle/908.php
- http://www.firstpr.com.au/dsp/pink-noise/#Voss-McCartney

lfnoise, lfnoiseO and lfnoiseN

Low-frequency noise generators (Butterworth-filtered downsampled white noise)

Usage

Example

(view waveforms in faust2octave):

phafla.lib

A library of compressor effects.

It should be used using the pf environment:

```
pf = library("phafla.lib");
process = pf.functionCall;
Another option is to import stdfaust.lib which already contains the pf environment:
import("stdfaust.lib");
```

Functions Reference

process = pf.functionCall;

flanger_mono

Mono flanging effect. flanger_mono is a standard Faust function.

Usage:

```
_ : flanger_mono(dmax,curdel,depth,fb,invert) : _;
```

Where:

- dmax: maximum delay-line length (power of 2) 10 ms typical
- curdel: current dynamic delay (not to exceed dmax)
- depth: effect strength between 0 and 1 (1 typical)
- fb: feedback gain between 0 and 1 (0 typical)
- invert: 0 for normal, 1 to invert sign of flanging sum

Reference

 $https://ccrma.stanford.edu/{\sim}jos/pasp/Flanging.html$

flanger_stereo

Stereo flanging effect.

Usage:

```
_,_: flanger_stereo(dmax,curdel1,curdel2,depth,fb,invert): _,_;
```

- dmax: maximum delay-line length (power of 2) 10 ms typical
- curdel: current dynamic delay (not to exceed dmax)
- depth: effect strength between 0 and 1 (1 typical)
- fb: feedback gain between 0 and 1 (0 typical)

• invert: 0 for normal, 1 to invert sign of flanging sum

Reference

https://ccrma.stanford.edu/~jos/pasp/Flanging.html

phaser2_mono

Mono phasing effect. phaser2_mono is a standard Faust function.

Phaser

_ : phaser2_mono(Notches,phase,width,frqmin,fratio,frqmax,speed,depth,fb,invert) : _;

Where:

- Notches: number of spectral notches (MACRO ARGUMENT not a signal)
- phase: phase of the oscillator (0-1)
- width: approximate width of spectral notches in Hz
- frqmin: approximate minimum frequency of first spectral notch in Hz
- fratio: ratio of adjacent notch frequencies
- frqmax: approximate maximum frequency of first spectral notch in Hz
- speed: LFO frequency in Hz (rate of periodic notch sweep cycles)
- depth: effect strength between 0 and 1 (1 typical) (aka "intensity") when depth=2, "vibrato mode" is obtained (pure allpass chain)
- fb: feedback gain between -1 and 1 (0 typical)
- invert: 0 for normal, 1 to invert sign of flanging sum

Reference:

- https://ccrma.stanford.edu/~jos/pasp/Phasing.html
- http://www.geofex.com/Article_Folders/phasers/phase.html
- 'An Allpass Approach to Digital Phasing and Flanging', Julius O. Smith III, Proc. Int. Computer Music Conf. (ICMC-84), pp. 103-109, Paris, 1984.
- CCRMA Tech. Report STAN-M-21: https://ccrma.stanford.edu/STANM/stanms/stanm21/

phaser2_stereo

Stereo phasing effect.

Phaser

_ : phaser2_stereo(Notches,phase,width,frqmin,fratio,frqmax,speed,depth,fb,invert) : _;

Where:

- Notches: number of spectral notches (MACRO ARGUMENT not a signal)
- phase: phase of the oscillator (0-1)
- width: approximate width of spectral notches in Hz
- frqmin: approximate minimum frequency of first spectral notch in Hz
- fratio: ratio of adjacent notch frequencies
- frqmax: approximate maximum frequency of first spectral notch in Hz
- speed: LFO frequency in Hz (rate of periodic notch sweep cycles)
- depth: effect strength between 0 and 1 (1 typical) (aka "intensity") when depth=2, "vibrato mode" is obtained (pure allpass chain)
- fb: feedback gain between -1 and 1 (0 typical)
- invert: 0 for normal, 1 to invert sign of flanging sum

Reference:

- https://ccrma.stanford.edu/~jos/pasp/Phasing.html
- http://www.geofex.com/Article Folders/phasers/phase.html
- 'An Allpass Approach to Digital Phasing and Flanging', Julius O. Smith III, Proc. Int. Computer Music Conf. (ICMC-84), pp. 103-109, Paris, 1984.
- CCRMA Tech. Report STAN-M-21: https://ccrma.stanford.edu/STANM/stanms/stanm21/

pm.lib

Faust physical modeling library.

It should be used using the fi environment:

```
pm = library("pm.lib");
process = pm.functionCall;
```

Another option is to import stdfaust.lib which already contains the pm environment:

```
import("stdfaust.lib");
process = pm.functionCall;
```

chain(A:B:...)

Creates a chain of bidirectional blocks. Blocks must have 3 inputs and outputs. The first input/output correspond to the left going signal, the second input/output correspond to the right going signal and the third input/output is the mix of the main signal output. The implied one sample delay created by the ~ operator is generalized to the left and right going waves. Thus, n blocks in chain() will add an n samples delay to both the left and right going waves. ### Usage

 $\label{lem:chain} right Going Waves, left Going Waves, mixed Output : chain (A:B) : right Going Waves, left Going Waves, mixed Output : chain (A:B) : right Going Waves, left Going Waves, mixed Output : chain (A:B) : right Going Waves, left Going Waves, mixed Output : chain (A:B) : right Going Waves, left Going Waves, mixed Output : chain (A:B) : right Going Waves, left Going Waves, mixed Output : chain (A:B) : right Going Waves, left Going Waves, mixed Output : chain (A:B) : right Going Waves, left Going Waves, mixed Output : chain (A:B) : right Going Waves, left Going Waves, mixed Output : chain (A:B) : right Going Waves, left Going Waves, mixed Output : chain (A:B) : right Going Waves, left Going Waves, mixed Output : chain (A:B) : right Going Waves, left Going Waves, mixed Output : chain (A:B) : right Going Waves, left Going Waves, mixed Output : chain (A:B) : right Going Waves, left Going Waves, mixed Output : chain (A:B) : right Going Waves, mixed Output : chain (A:B)$

```
A = _,_,_;
B = _,_,_;
};
```

Requires

```
filter.lib (crossnn)
```

input(x)

Adds a waveguide input anywhere between 2 blocks in a chain of blocks (see chain()). ### Usage

```
string(x) = chain(A:input(x):B)
```

Where x is the input signal to be added to the chain.

output()

Adds a waveguide output anywhere between 2 blocks in a chain of blocks and sends it to the mix output channel (see chain()). ### Usage

```
chain(A:output:B)
```

terminations(a,b,c)

Creates terminations on both sides of a chain() without closing the inputs and outputs of the bidirectional signals chain. As for chain(), this function adds a

```
1 sample delay to the bidirectional signal both ways. ### Usage
rightGoingWaves,leftGoingWaves,mixedOutput : terminations(a,b,c) : rightGoingWaves,leftGoing
with{
     a = *(-1); // left termination
     b = chain(D:E:F); // bidirectional chain of blocks (D, E, F, etc.)
     c = *(-1); // right termination
};
Requires
filter.lib (crossnn)
fullTerminations(a,b,c)
Same as terminations() but closes the inputs and outputs of the bidirectional
chain (only the mixed output remains). \#\#\# Usage
terminations(a,b,c):
with{
     a = *(-1); // left termination
     b = chain(D:E:F); // bidirectional chain of blocks (D, E, F, etc.)
     c = *(-1); // right termination
};
Requires
filter.lib (crossnn)
leftTermination(a,b)
```

Creates a termination on the left side of a chain() without closing the inputs and outputs of the bidirectional signals chain. This function adds a 1 sample delay near the termination. ## Usage

```
rightGoingWaves,leftGoingWaves,mixedOutput : terminations(a,b) : rightGoingWaves,leftGoingWaves
with{
    a = *(-1); // left termination
    b = chain(D:E:F); // bidirectional chain of blocks (D, E, F, etc.)
```

};

Requires

```
filter.lib (crossnn)
```

rightTermination(b,c)

Creates a termination on the right side of a chain() without closing the inputs and outputs of the bidirectional signals chain. This function adds a 1 sample delay near the termination. ### Usage

```
rightGoingWaves,leftGoingWaves,mixedOutput : terminations(b,c) : rightGoingWaves,leftGoingWaves
with{
    b = chain(D:E:F); // bidirectional chain of blocks (D, E, F, etc.)
    c = *(-1); // right termination
};
```

rightGoingWaves,leftGoingWaves,mixedOutput : waveguide(nMax,n) : rightGoingWaves,leftGoingWaves,leftGoingWaves

Requires

```
filter.lib (crossnn)
```

waveguide(nMax,n)

A simple waveguide block based on a 4th order fractional delay. ### Usage

```
With: * nMax: the maximum length of the waveguide in samples * n the length of the waveguide in samples. ### Requires filter.lib (fdelay4)
```

idealString(length,reflexion,xPosition,x)

An ideal string with rigid terminations and where the plucking position and the pick-up position are the same. ### Usage

```
1-1' : idealString(length,reflexion,xPosition,x)
```

With: * length: the length of the string in meters * reflexion: the coefficient of reflexion (0-0.9999999) * pluckPosition: the plucking position (0.001-0.999) * x: the input signal for the excitation ### Requires filter.lib (fdelay4,crossnn)

reverb.lib

A library of reverb effects.

It should be used using the re environment:

```
re = library("reverb.lib");
process = re.functionCall;
```

Another option is to import stdfaust.lib which already contains the re environment:

```
import("stdfaust.lib");
process = re.functionCall;
```

Functions Reference

jcrev

This artificial reverberator take a mono signal and output stereo (satrev) and quad (jcrev). They were implemented by John Chowning in the MUS10 computer-music language (descended from Music V by Max Mathews). They are Schroeder Reverberators, well tuned for their size. Nowadays, the more expensive freeverb is more commonly used (see the Faust examples directory).

jcrev reverb below was made from a listing of "RV", dated April 14, 1972, which was recovered from an old SAIL DART backup tape. John Chowning thinks this might be the one that became the well known and often copied JCREV.

jcrev is a standard Faust function

Usage

```
_ : jcrev : _,_,_
```

satrev

This artificial reverberator take a mono signal and output stereo (satrev) and quad (jcrev). They were implemented by John Chowning in the MUS10 computer-music language (descended from Music V by Max Mathews). They are Schroeder Reverberators, well tuned for their size. Nowadays, the more expensive freeverb is more commonly used (see the Faust examples directory).

satrev was made from a listing of "SATREV", dated May 15, 1971, which was recovered from an old SAIL DART backup tape. John Chowning thinks this might be the one used on his often-heard brass canon sound examples, one of which can be found at https://ccrma.stanford.edu/~jos/wav/FM_BrassCanon2.wav

Usage

```
_ : satrev : _,_
```

mono_freeverb

A simple Schroeder reverberator primarily developed by "Jezar at Dreampoint" that is extensively used in the free-software world. It uses four Schroeder allpasses in series and eight parallel Schroeder-Moorer filtered-feedback comb-filters for each audio channel, and is said to be especially well tuned.

Usage

```
_ : mono_freeverb(fb1, fb2, damp, spread) : _;
```

Where:

- fb1: coefficient of the lowpass comb filters (0-1)
- fb2: coefficient of the allpass comb filters (0-1)
- damp: damping of the lowpass comb filter (0-1)
- spread: spatial spread in number of samples (for stereo)

stereo_freeverb

A simple Schroeder reverberator primarily developed by "Jezar at Dreampoint" that is extensively used in the free-software world. It uses four Schroeder allpasses in series and eight parallel Schroeder-Moorer filtered-feedback comb-filters for each audio channel, and is said to be especially well tuned.

Usage

```
_,_ : stereo_freeverb(fb1, fb2, damp, spread) : _,_;
```

- **fb1**: coefficient of the lowpass comb filters (0-1)
- fb2: coefficient of the allpass comb filters (0-1)
- damp: damping of the lowpass comb filter (0-1)

• spread: spatial spread in number of samples (for stereo)

fdnrev0

Pure Feedback Delay Network Reverberator (generalized for easy scaling).

Usage

```
<1,2,4,...,N signals> <: fdnrev0(MAXDELAY,delays,BBSO,freqs,durs,loopgainmax,nonl) :> <1,2,4,...,N signals>
```

Where:

- N: 2, 4, 8, ... (power of 2)
- MAXDELAY: power of 2 at least as large as longest delay-line length
- delays: N delay lines, N a power of 2, lengths perferably coprime
- BBSO: odd positive integer = order of bandsplit desired at freqs
- freqs: NB-1 crossover frequencies separating desired frequency bands
- durs: NB decay times (t60) desired for the various bands
- loopgainmax: scalar gain between 0 and 1 used to "squelch" the reverb
- nonl: nonlinearity (0 to 0.999..., 0 being linear)

Reference

https://ccrma.stanford.edu/~jos/pasp/FDN_Reverberation.html

zita_rev_fdn

Internal 8x8 late-reverberation FDN used in the FOSS Linux reverb zita-rev1 by Fons Adriaensen fons@linuxaudio.org. This is an FDN reverb with allpass comb filters in each feedback delay in addition to the damping filters.

Usage

```
bus(8) : zita_rev_fdn(f1,f2,t60dc,t60m,fsmax) : bus(8)
```

- f1: crossover frequency (Hz) separating dc and midrange frequencies
- f2: frequency (Hz) above f1 where T60 = t60 m/2 (see below)
- t60dc: desired decay time (t60) at frequency 0 (sec)
- t60m: desired decay time (t60) at midrange frequencies (sec)

• fsmax: maximum sampling rate to be used (Hz)

Reference

- http://www.kokkinizita.net/linuxaudio/zita-rev1-doc/quickguide.html
- https://ccrma.stanford.edu/~jos/pasp/Zita_Rev1.html

zita_rev1_stereo

Extend zita_rev_fdn to include zita_rev1 input/output mapping in stereo mode.

Usage

```
_,_ : zita_rev1_stereo(rdel,f1,f2,t60dc,t60m,fsmax) : _,_
```

Where:

 $\mbox{\tt rdel} = \mbox{\tt delay (in ms) before reverberation begins (e.g., 0 to \sim100 ms) (remaining args and refs as for ${\tt zita_rev_fdn}$ above)}$

zita_rev1_ambi

Extend zita_rev_fdn to include zita_rev1 input/output mapping in "ambisonics mode", as provided in the Linux C++ version.

Usage

```
_,_ : zita_rev1_ambi(rgxyz,rdel,f1,f2,t60dc,t60m,fsmax) : _,_,_,
Where:
```

 $rgxyz = relative gain of lanes 1,4,2 to lane 0 in output (e.g., -9 to 9) (remaining args and references as for zita_rev1_stereo above)$

route.lib

A library of basic elements to handle signal routing in Faust.

It should be used using the si environment:

```
ro = library("route.lib");
process = ro.functionCall;
Another option is to import stdfaust.lib which already contains the si envi-
ronment:
import("stdfaust.lib");
process = ro.functionCall;
Functions Reference
cross
Cross n signals: (x1,x2,...,xn) \rightarrow (xn,...,x2,x1). cross is a standard Faust
function.
Usage
cross(n)
_,_,_ : cross(3) : _,_,_
Where:
   • n: number of signals (int, must be known at compile time)
Note
Special case: cross2:
cross2 = _, cross(2),_;
crossnn
Cross two bus(n)s.
Usage
_,_,... : crossmm(n) : _,_,...
Where:
   • n: the number of signals in the bus
```

crossn1

Cross bus(n) and bus(1).

Usage

```
_,_,... : crossn1(n) : _,_,...
```

Where:

• n: the number of signals in the first bus

interleave

Interleave row col cables from column order to row order. input: x(0), x(1), x(2) ..., x(row col-1) output: x(0+0row), x(0+1row), x(0+2row), ..., $x(1+\theta row)$, x(1+1row), x(1+2row), ...

Usage

```
_,_,_,_ : interleave(row,column) : _,_,_,_,
```

Where:

- row: the number of row (int, known at compile time)
- column: the number of column (int, known at compile time)

butterfly

Addition (first half) then substraction (second half) of interleaved signals.

Usage

```
_{-},_{-},_{-}: butterfly(n) : _{-},_{-},_{-}
```

Where:

• n: size of the butterfly (n is int, even and known at compile time)

hadamard

Hadamard matrix function of size $n = 2^k$.

Usage

```
_,_,_ : hadamard(n) : _,_,_,
```

Where:

• n: 2^k, size of the matrix (int, must be known at compile time)

Note:

Implementation contributed by Remy Muller.

recursivize

Create a recursion from two arbitrary processors p and q.

Usage

```
_,_ : recursivize(p,q) : _,_
```

Where:

- p: the forward arbitrary processor
- q: the feedback arbitrary processor

signal.lib

A library of basic elements to handle signals in Faust.

It should be used using the si environment:

```
si = library("signal.lib");
process = si.functionCall;
```

Another option is to import stdfaust.lib which already contains the si environment:

```
import("stdfaust.lib");
process = si.functionCall;
```

Functions Reference

bus

n parallel cables. bus is a standard Faust function.

Usage

```
bus(n)
bus(4) : _,_,_,
```

Where:

• n: is an integer known at compile time that indicates the number of parallel cables.

block

Block - terminate n signals. block is a standard Faust function.

Usage

```
\_,\_,\dots : block(n) : \_,\dots
```

Where:

• n: the number of signals to be blocked

${\tt interpolate}$

Linear interpolation between two signals.

Usage

```
_,_ : interpolate(i) : _
```

Where:

• i: interpolation control between 0 and 1 (0: first input; 1: second input)

smooth

Exponential smoothing by a unity-dc-gain one-pole lowpass. smooth is a standard Faust function.

Usage:

```
_ : smooth(tau2pole(tau)) : _
```

Where:

• tau: desired smoothing time constant in seconds, or

```
hslider(...) : smooth(s) : _
```

Where:

• s: smoothness between 0 and 1. s=0 for no smoothing, s=0.999 is "very smooth", s>1 is unstable, and s=1 yields the zero signal for all inputs. The exponential time-constant is approximately 1/(1-s) samples, when s is close to (but less than) 1.

Reference:

 $https://ccrma.stanford.edu/\sim jos/mdft/Convolution_Example_2_ADSR.html$

smoo

Smoothing function based on smooth ideal to smooth UI signals (sliders, etc.) down. smoo is a standard Faust function.

Usage

```
hslider(...) : smoo;
```

polySmooth

A smoothing function based on smooth that doesn't smooth when a trigger signal is given. This is very useful when making polyphonic synthesizer to make sure that the value of the parameter is the right one when the note is started.

Usage

hslider(...) : polysmooth(g,s,d) : _

Where:

- g: the gate/trigger signal used when making polyphonic synths
- s: the smoothness (see smooth)
- d: the number of samples to wait before the signal start being smoothed after ${\sf g}$ switched to 1

bsmooth

Block smooth linear interpolation during a block of samples.

Usage

```
hslider(...) : bsmooth : _
```

lag_ud

Lag filter with separate times for up and down.

Usage

```
_ : lag_ud(up, dn, signal) : _;
```

dot

Dot product for two vectors of size n.

Usage

```
_,_,_,_ : dot(n) : _
```

Where:

• n: size of the vectors (int, must be known at compile time)

spat.lib

This library contains a collection of tools for sound spatialization. It should be used using the sp environment: sp = library("spat.lib"); process = sp.functionCall; Another option is to import stdfaust.lib which already contains the sp environment: import("stdfaust.lib"); process = sp.functionCall; panner A simple linear gain panner. Usage _ : panner(g) : _,_ Where: • g: the panning (0-1) spat GMEM SPAT: n-outputs spatializer Usage _ : spat(n,r,d) : _,_,... Where: • n: number of outputs • r: rotation (between 0 et 1) • d: distance of the source (between 0 et 1)

stereoize

Transform an arbitrary processor ${\sf p}$ into a stereo processor with 2 inputs and 2 outputs.

Usage

```
_,_ : stereoize(p) : _,_
```

Where:

• p: the arbitrary processor

synth.lib

This library contains a collection of envelope generators.

It should be used using the sy environment:

```
sy = library("synth.lib");
process = sy.functionCall;
```

Another option is to import stdfaust.lib which already contains the sy environment:

```
import("stdfaust.lib");
process = sy.functionCall;
```

popFilterPerc

A simple percussion instrument based on a "popped" resonant bandpass filter. popFilterPerc is a standard Faust function.

Usage

```
popFilterDrum(freq,q,gate) : _;
```

- freq: the resonance frequency of the instrument
- q: the q of the res filter (typically, 5 is a good value)
- gate: the trigger signal (0 or 1)

dubDub

A simple synth based on a sawtooth wave filtered by a resonant lowpass. dubDub is a standard Faust function.

Usage

```
dubDub(freq,ctFreq,q,gate) : _;
```

Where:

- freq: frequency of the sawtooth
- ctFreq: cutoff frequency of the filter
- q: Q of the filter
- gate: the trigger signal (0 or 1)

sawTrombone

A simple trombone based on a lowpassed sawtooth wave. sawTrombone is a standard Faust function.

Usage

```
sawTrombone(att,freq,gain,gate) : _
```

Where:

- att: exponential attack duration in s (typically 0.01)
- freq: the frequency
- gain: the gain (0-1)
- gate: the gate (0 or 1)

combString

Simplest string physical model ever based on a comb filter. combString is a standard Faust function.

Usage

```
combString(freq,res,gate) : _;
```

Where:

• freq: the frequency of the string

```
• res: string T60 (resonance time) in second
```

• gate: trigger signal (0 or 1)

additiveDrum

A simple drum using additive synthesis. additiveDrum is a standard Faust function.

Usage

```
additiveDrum(freq,freqRatio,gain,harmDec,att,rel,gate) : _
```

Where:

- freq: the resonance frequency of the drum
- freqRatio: a list of ratio to choose the frequency of the mode in function of freq e.g.(1 1.2 1.5 ...). The first element should always be one (fundamental).
- gain: the gain of each mode as a list (1 0.9 0.8 ...). The first element is the gain of the fundamental.
- harmDec: harmonic decay ratio (0-1): configure the speed at which higher modes decay compare to lower modes.
- att: attack duration in second
- rel: release duration in second
- gate: trigger signal (0 or 1)

fm

An FM synthesizer with an arbitrary number of modulators connected as a sequence. fm is a standard Faust function.

Usage

```
freqs = (300,400,...);
indices = (20,...);
fm(freqs,indices) : _
```

- freqs: a list of frequencies where the first one is the frequency of the carrier and the others, the frequency of the modulator(s)
- indices: the indices of modulation (Nfreqs-1)

vaeffect.lib

A library of virtual analog filter effects.

It should be used using the ve environment:

```
ve = library("vaeffect.lib");
process = ve.functionCall;
```

Another option is to import stdfaust.lib which already contains the ve environment:

```
import("stdfaust.lib");
process = ve.functionCall;
```

Functions Reference

moog_vcf

Moog "Voltage Controlled Filter" (VCF) in "analog" form. Moog VCF implemented using the same logical block diagram as the classic analog circuit. As such, it neglects the one-sample delay associated with the feedback path around the four one-poles. This extra delay alters the response, especially at high frequencies (see reference [1] for details). See moog_vcf_2b below for a more accurate implementation.

Usage

```
moog_vcf(res,fr)
```

Where:

- fr: corner-resonance frequency in Hz (less than SR/6.3 or so)
- res: Normalized amount of corner-resonance between 0 and 1 (0 is no resonance, 1 is maximum)

References

- https://ccrma.stanford.edu/~stilti/papers/moogvcf.pdf
- https://ccrma.stanford.edu/~jos/pasp/vegf.html

moog_vcf_2b[n]

Moog "Voltage Controlled Filter" (VCF) as two biquads. Implementation of the ideal Moog VCF transfer function factored into second-order sections. As

a result, it is more accurate than moog_vcf above, but its coefficient formulas are more complex when one or both parameters are varied. Here, res is the fourth root of that in moog_vcf, so, as the sampling rate approaches infinity, moog_vcf(res,fr) becomes equivalent to moog_vcf_2b[n](res^4,fr) (when res and fr are constant). moog_vcf_2b uses two direct-form biquads (tf2). moog_vcf_2bn uses two protected normalized-ladder biquads (tf2np).

Usage

```
moog_vcf_2b(res,fr)
moog_vcf_2bn(res,fr)
```

Where:

- fr: corner-resonance frequency in Hz
- res: Normalized amount of corner-resonance between 0 and 1 (0 is min resonance, 1 is maximum)

wah4

Wah effect, 4th order. wah4 is a standard Faust function.

Usage

```
_ : wah4(fr) : _
```

Where:

• fr: resonance frequency in Hz

Reference

 $https://ccrma.stanford.edu/\sim jos/pasp/vegf.html$

autowah

Auto-wah effect. autowah is a standard Faust function.

Usage

```
_ : autowah(level) : _;
```

Where:

• level: amount of effect desired (0 to 1).

crybaby

Digitized CryBaby wah pedal. crybaby is a standard Faust function.

Usage

```
_ : crybaby(wah) : _
```

Where:

• wah: "pedal angle" from 0 to 1

Reference

 $https://ccrma.stanford.edu/\sim jos/pasp/vegf.html$

vocoder

A very simple vocoder where the spectrum of the modulation signal is analyzed using a filter bank. vocoder is a standard Faust function.

Usage

```
_ : vocoder(nBands,att,rel,BWRatio,source,excitation) : _;
```

- nBands: Number of vocoder bands
- att: Attack time in seconds
- rel: Release time in seconds
- BWRatio: Coefficient to adjust the bandwidth of each band (0.1 2)
- source: Modulation signal
- excitation: Excitation/Carrier signal