Amazon Simple Storage Service

Developer Guide API Version 2006-03-01



Amazon Simple Storage Service: Developer Guide Copyright © 2010 Amazon Web Services LLC or its affiliates. All rights reserved.

Table of Contents

Welcome to Amazon S3	
Making Requests	10
Making Requests using AWS SDKs	13
Making Requests Using AWS Account or IAM User Credentials	14
Making Requests Using AWS Account or IAM User Credentials - AWS SDK for Java	14
Making Requests Using AWS Account or IAM User Credentials - AWS SDK for	
Making Requests Using AWS Account or IAM User Credentials - AWS SDK for PHP	
Making Requests Using AWS Account or IAM User Credentials - AWS SDK for Ruby	
Making Requests Using IAM User Temporary Credentials	
Making Requests Using IAM User Temporary Credentials - AWS SDK for Java	
Making Requests Using IAM User Temporary Credentials - AWS SDK for .NET	
Making Requests Using IAM User Temporary Credentials - AWS SDK for PHP	
Making Requests Using IAM User Temporary Credentials - AWS SDK for Ruby	
Making Requests Using Federated User Temporary Credentials	
Making Requests Using Federated User Temporary Credentials - AWS SDK for	20
Java	29
Making Requests Using Federated User Temporary Credentials - AWS SDK for	
Making Requests Using Federated User Temporary Credentials - AWS SDK for PHP	
Making Requests Using Federated User Temporary Credentials - AWS SDK for	
Ruby	43
Making Requests using the REST API	
Authenticating Requests Using the REST API	
Signing and Authenticating REST Requests	
Virtual Hosting of Buckets	
Request Redirection and the REST API	
Browser-Based Uploads Using POST	
HTML Forms	
Upload Examples	
POST with Adobe Flash	
Working with Amazon S3 Buckets	
Bucket Restrictions and Limitations	
Bucket Configuration Options	
Buckets and Regions	
Managing Bucket Website Configuration	
Managing Websites with the AWS Management Console	
Managing Websites with the AWS SDK for Java	
Managing Websites with the AWS SDK for .NET	
Managing Websites with the AWS SDK for PHP	
Managing Websites with the REST API	
Requester Pays Buckets	
Setting the requestPayment Bucket Configuration	
Retrieving requestPayment Configuration	
Downloading Objects in Requester Pays Buckets	
DevPay and Requester Pays	
Charge Details	
Buckets and Access Control	
Billing and Reporting of Buckets	
Working with Amazon S3 Objects	100

Object Key and Metadata	
Object Subresources	
Object Versioning	
Operations on Objects	
Multipart Upload Overview	
Quick Facts	
API Support for Multipart Upload	
Multipart Upload API and Permissions	. 108
Getting Objects	. 109
Get an Object Using the AWS SDK for Java	. 110
Get an Object Using the AWS SDK for .NET	
Get an Object Using the AWS SDK for PHP	. 116
Get an Object Using REST API	. 118
Share an Object with Others	. 118
Generate Pre-signed Object URL using AWS Explorer for Visual Studio	
Generate Pre-signed Object URL using AWS SDK for Java	. 119
Generate Pre-signed Object URL using AWS SDK for .NET	. 121
Uploading Objects	. 123
Uploading Objects in a Single Operation	
Upload an Object Using the AWS SDK for Java	. 124
Upload an Object Using the AWS SDK for .NET	
Upload an Object Using the AWS SDK for PHP	
Upload an Object Using the AWS SDK for Ruby	. 132
Upload an Object Using the REST API	
Uploading Objects Using Multipart Upload API	
Using the AWS SDK for Java for Multipart Upload	
Using the High-Level Java API for Multipart Upload	
Upload a File	
Abort Multipart Uploads	
Track Multipart Upload Progress	
Using the Low-Level Java API for Multipart Upload	
Upload a File	
List Multipart Uploads	
Abort a Multipart Upload	
Using the AWS SDK for .NET for Multipart Upload	. 145
Using the High-Level .NET API for Multipart Upload	
Upload a File	
Upload a Directory	
Abort Multipart Uploads	
Track Multipart Upload Progress	
Using the Low-Level .NET API for Multipart Upload	
Upload a File	
List Multipart Uploads	
Track Multipart Upload Progress	
Abort a Multipart Upload	
Using the AWS SDK for PHP for Multipart Upload	
Using the High-Level PHP API for Multipart Upload	
Upload a File	
Using the Low-Level PHP API for Multipart Upload	
Upload a File	
List Multipart Uploads	
Abort a Multipart Upload	
Using the REST API for Multipart Upload	
Uploading Objects Using Pre-Signed URLs	
Upload an Object Using Pre-Signed URL - AWS SDK for Java	
Upload an Object Using Pre-Signed URL - AWS SDK for .NET	
Copying Objects	
Copying Objects in a Single Operation	

Copy an Object Using the AWS SDK for Java	175
Copy an Object Using the AWS SDK for .NET	
Copy an Object Using the AWS SDK for PHP	
Copy an Object Using the AWS SDK for Ruby	
Copy an Object Using the REST API	
Copying Objects Using the Multipart Upload API	
Copy an Object Using the AWS SDK for Java Multipart Upload API	
Copy an Object Using the AWS SDK for .NET Multipart Upload API	
Copy Object Using the REST Multipart Upload API	
Listing Object Keys	
Iterating Through Multi-Page Results	
Listing Keys Hierarchically Using Prefix and Delimiter	
Listing Keys Using the AWS SDK for Java	195
Listing Keys Using the AWS SDK for .NET	198
Listing Keys Using the AWS SDK for PHP	202
Access Control	
Using IAM Policies	
Using Bucket Policies	
Writing Bucket Policies	
Setting Bucket Policies on a Bucket	
Returning the Bucket Policies on a Bucket	
Deleting Bucket Policies on a Bucket	
Example Cases for Amazon S3 Bucket Policies	
How to Use Resources, Principals, Operations, and Conditions in Bucket Policies	
Using ACLs	
Access Control List (ACL) Overview	
Canned ACL	
Managing ACLs	232
Managing ACLs in the AWS Management Console	232
Managing ACLs Using the AWS SDK for Java	233
Managing ACLs Using the AWS SDK for .NET	
Managing ACLs Using the REST API	
When to Use ACLs vs Bucket Policies	
Using ACLs and Bucket Policies Together	
Using Query String Authentication	
Data Protection	
Using Data Encryption	
Using Server-Side Encryption	
Specifying Server-Side Encryption Using the AWS SDK for Java	
Specifying Server-Side Encryption Using the AWS SDK for .NET	
Specifying Server-Side Encryption Using the AWS SDK for PHP	
Specifying Server-Side Encryption Using the AWS SDK for Ruby	
Specifying Server-Side Encryption Using REST API	
Specifying Server-Side Encryption Using the AWS Management Console	
Using Client-Side Encryption	
Specifying Client-Side Encryption Using the AWS SDK for Java	255
Customizing Your Client-Side Encryption Environment	258
Using Reduced Redundancy Storage	260
Setting the Storage Class of an Object You Upload	260
Changing the Storage Class of an Object in Amazon S3	
Return Code For Lost Data	
Using Versioning	
Enabling a Bucket's Versioning State	
MFA Delete	
Enabling Versioning	
Configuring a Bucket with MFA Delete	
Suspending Versioning	∠05
Determining the Versioning State	266

Adding Objects to Versioning-Enabled Buckets	267
Listing the Objects in a Versioning-Enabled Bucket	
Retrieving a Subset of Objects in Buckets	
Retrieving All Versions of a Key	
Retrieving Additional Object Versions after Exceeding Max-Keys	
Retrieving Object Versions	
Retrieving the Metadata of an Object Version	
Deleting Object Versions	
Using MFA Delete	
Working With Delete Markers	
Removing Delete Markers	
Restoring Previous Versions	
Versioned Object Permissions and ACLs	
Working with Versioning-Suspended Buckets	
Adding Objects to Versioning-Suspended Buckets	
Retrieving Objects from Versioning-Suspended Buckets	
Deleting Objects from Versioning-Suspended Buckets Deleting Objects from Versioning-Suspended Buckets	
Hosting Websites on Amazon S3	
Setting Up a Website	
Website Endpoints	
Index Document Support	
Custom Error Document Support	
How Do I Configure My Bucket As a Website?	
Permissions Required for Website Access	
Setting Up Notification of Bucket Events	
Request Routing	
Request Redirection and the REST API	
DNS Considerations	
Performance Optimization	
TCP Window Scaling	
TCP Selective Acknowledgement	
Using BitTorrent with Amazon S3	
How You are Charged for BitTorrent Delivery	
Using BitTorrent to Retrieve Objects Stored in Amazon S3	
Publishing Content Using Amazon S3 and BitTorrent	
Using Amazon DevPay with Amazon S3	
Amazon S3 Customer Data Isolation	
Amazon DevPay Token Mechanism	
Amazon S3 and Amazon DevPay Authentication	
Amazon S3 Bucket Limitation	
Amazon S3 and Amazon DevPay Process	
Additional Information	307
Handling Errors	308
The REST Error Response	308
Error Response	309
Error Code	309
Error Message	309
Further Details	309
The SOAP Error Response	309
Amazon S3 Error Best Practices	310
Server Access Logging	
Server Access Logging Configuration API	
Delivery of Server Access Logs	
Server Access Log Format	
Setting Up Server Access Logging	
Using the AWS SDKs and Explorers	
Using the AWS SDK for Java	
Using the AWS SDK for NET	327

Using the AWS SDK for PHP	329
Using the AWS SDK for Ruby	329
Appendices	
Appendix A: The Access Policy Language	
Overview	
Key Concepts	
Architectural Overview	
Using the Access Policy Language	
Evaluation Logic	
How to Write a Policy	
Basic Policy Structure	
Element Descriptions	
Supported Data Types	
Special Information for Amazon S3 Policies	
Appendix B: Using the SOAP API	
Common SOAP API Elements	
Authenticating SOAP Requests	
Setting Access Policy with SOAP	
Amazon S3 Resources	
Document History	
Glossary	
Index	

Welcome to Amazon S3

This is the *Amazon Simple Storage Service (Amazon S3) Developer Guide*. It explains Amazon S3 core concepts of buckets, objects and how to work with these resources using the available APIs. It describes how you send requests to create buckets, store and retrieve your objects, and manage permissions to your resources. The guide describes both the access control and the authentication process. The access control defines who can access objects and buckets within Amazon S3, and the type of access (e.g., READ, WRITE, and so on). The authentication process verifies identity of a user trying to access Amazon Web Services (AWS).

Amazon Simple Storage Service (Amazon S3) is a web service that enables you to store data in the cloud. You can then download the data or use the data with other AWS services, such as Amazon Elastic Cloud Computer (see Amazon Elastic Compute Cloud (Amazon EC2)).

How Do I...?

Information	Relevant Sections
General product overview and pricing	Amazon Simple Storage Service (Amazon S3)
Get a quick hands-on introduction to Amazon S3	Amazon Simple Storage Service (Amazon S3) Getting Started Guide
Learn about Amazon S3 key terminology and concepts	Introduction to Amazon S3 (p. 2)
How do I work with buckets	Working with Amazon S3 Buckets (p. 82)
How do I work with objects	Working with Amazon S3 Objects (p. 100)
How do I make requests	Making Requests (p. 10)
How do I manage access to my resources	Access Control (p. 204)

Introduction to Amazon S3

Topics

- Overview of Amazon S3 (p. 2)
- Advantages to Amazon S3 (p. 2)
- Amazon S3 Concepts (p. 3)
- Features (p. 6)
- Amazon S3 Application Programming Interfaces (API) (p. 8)
- Paying for Amazon S3 (p. 9)
- Related Amazon Web Services (p. 9)

This introduction to Amazon S3 is intended to give you a detailed summary of this web service. After reading this section, you should have a good idea of what it offers and how it can fit in with your business.

Overview of Amazon S3

Amazon S3 is storage for the Internet. It is designed to make web-scale computing easier for developers.

Amazon S3 has a simple web services interface that can be used to store and retrieve any amount of data, at any time, from anywhere on the web. It gives any developer access to the same highly scalable, reliable, fast, inexpensive data storage infrastructure that Amazon uses to run its own global network of web sites. The service aims to maximize benefits of scale and to pass those benefits to developers.

Advantages to Amazon S3

Amazon S3 is intentionally built with a minimal feature set that focuses on simplicity and robustness. Following are some of advantages of the Amazon S3 service:

- Create Buckets—Create and name a bucket that stores data Buckets are the fundamental container in Amazon S3 for data storage.
- Store data in Buckets—Store an infinite amount of data in a bucket
 Upload as many objects as you like into an Amazon S3 bucket. Each object can contain up to 5 TB of
 data. Each object is stored and retrieved using a unique developer-assigned key.
- Download data—Download your data or enable others to

Amazon Simple Storage Service Developer Guide Amazon S3 Concepts

Download your data any time you like or allow others to do the same.

- Permissions—Grant or deny access to others who want to upload or download data into your Amazon S3 bucket
 - Grant upload and download permissions to three types of users. Authentication mechanisms to ensure that data is kept secure from unauthorized access.
- Standard interfaces—Use standards-based REST and SOAP interfaces designed to work with any Internet-development toolkit.

Amazon S3 Concepts

Topics

- Buckets (p. 3)
- Objects (p. 3)
- Keys (p. 3)
- Regions (p. 4)
- Amazon S3 Data Consistency Model (p. 4)

This section describes key concepts and terminology you need to understand to use Amazon S3 effectively. They are presented in the order you will most like encounter them.

Buckets

A bucket is a container for objects stored in Amazon S3. Every object is contained in a bucket. For example, if the object named photos/puppy.jpg is stored in the johnsmith bucket, then it is addressable using the URL http://johnsmith.s3.amazonaws.com/photos/puppy.jpg

Buckets serve several purposes: they organize the Amazon S3 namespace at the highest level, they identify the account responsible for storage and data transfer charges, they play a role in access control, and they serve as the unit of aggregation for usage reporting.

You can configure buckets so that they are created in a specific Region. For more information, see Buckets and Regions (p. 84). You can also configure a bucket so that every time an object is added to it, Amazon S3 generates a unique version ID and assigns it to the object. For more information, see Versioning (p. 262).

For more information about buckets, see Working with Amazon S3 Buckets (p. 82).

Objects

Objects are the fundamental entities stored in Amazon S3. Objects consist of object data and metadata. The data portion is opaque to Amazon S3. The metadata is a set of name-value pairs that describe the object. These include some default metadata such as the date last modified, and standard HTTP metadata such as Content-Type. The developer can also specify custom metadata at the time the Object is stored.

An object is uniquely identified within a bucket by a key (name) and a version ID. For more information, see Keys (p. 3) and Versioning (p. 262).

Keys

A key is the unique identifier for an object within a bucket. Every object in a bucket has exactly one key. Because the combination of a bucket, key, and version ID uniquely identify each object, Amazon S3 can be thought of as a basic data map between "bucket + key + version" and the object itself. Every object

in Amazon S3 can be uniquely addressed through the combination of the web service endpoint, bucket name, key, and optionally, a version. For example, in the URL

http://doc.s3.amazonaws.com/2006-03-01/AmazonS3.wsdl, "doc" is the name of the bucket and "2006-03-01/AmazonS3.wsdl" is the key.

Regions

You can choose the geographical Region where Amazon S3 will store the buckets you create. You might choose a Region to optimize latency, minimize costs, or address regulatory requirements. Amazon S3 currently supports the following Regions:

- US Standard—Uses Amazon S3 servers in the United States
 This is the default Region. The US Standard Region automatically routes requests to facilities in Northern Virginia or the Pacific Northwest using network maps. To use this region, select US Standard as the region when creating a bucket in the console. The US Standard Region provides eventual consistency for all requests.
- US West (Northern California) Region—Uses Amazon S3 servers in Northern California
 To use this Region, choose Northern California as the Region when creating the bucket in the AWS
 Management Console.
 - In Amazon S3, the US West (Northern California) Region provides read-after-write consistency for PUTS of new objects in your Amazon S3 bucket and eventual consistency for overwrite PUTS and DELETES.
- EU (Ireland) Region—Uses Amazon S3 servers in Ireland
 To use this Region, choose Ireland as the Region when creating the bucket in the AWS Management Console. In Amazon S3, the EU (Ireland) Region provides read-after-write consistency for PUTS of new objects in your Amazon S3 bucket and eventual consistency for overwrite PUTS and DELETES.
- Asia Pacific (Singapore) Region—Uses Amazon S3 servers in Singapore.
 To use this Region, choose Singapore as the Region when creating the bucket in the AWS Management Console. In Amazon S3, the Asia Pacific (Singapore) Region provides read-after-write consistency for PUTS of new objects in your Amazon S3 bucket and eventual consistency for overwrite PUTS and DELETES.
- Asia Pacific (Tokyo) Region—Uses Amazon S3 servers in Tokyo.
 To use this Region, choose Tokyo as the Region when creating the bucket in the AWS Management Console. In Amazon S3, the Asia Pacific (Tokyo) Region provides read-after-write consistency for PUTS of new objects in your Amazon S3 bucket and eventual consistency for overwrite PUTS and DELETES.

Objects stored in a Region never leave the Region unless you explicitly transfer them to another Region. For example, objects stored in the EU (Ireland) Region never leave it.

Amazon S3 Data Consistency Model

Updates to a single key are atomic. For example, if you PUT to an existing key, a subsequent read might return the old data or the updated data, but it will never write corrupted or partial data.

Amazon S3 achieves high availability by replicating data across multiple servers within Amazon's data centers. After a "success" is returned, your data is safely stored. However, information about the changes might not immediately replicate across Amazon S3 and you might observe the following behaviors:

- A process writes a new object to Amazon S3 and immediately attempts to read it. Until the change is fully propagated. Amazon S3 might report "key does not exist."
- A process writes a new object to Amazon S3 and immediately lists keys within its bucket. Until the change is fully propagated, the object might not appear in the list.

Amazon Simple Storage Service Developer Guide Amazon S3 Data Consistency Model

- A process replaces an existing object and immediately attempts to read it. Until the change is fully propagated, Amazon S3 might return the prior data.
- A process deletes an existing object and immediately attempts to read it. Until the deletion is fully propagated, Amazon S3 might return the deleted data.
- A process deletes an existing object and immediately lists keys within its bucket. Until the deletion is fully propagated, Amazon S3 might list the deleted object.

The US Standard Region provides eventual consistency for all requests. The EU (Ireland) and Northern California Regions provide read-after-write consistency for PUTS of new objects and eventual consistency for overwrite PUTS and DELETES.



Note

Amazon S3 does not currently support object locking. If two puts are simultaneously made to the same key, the put with the latest time stamp wins. If this is an issue, you will need to build an object-locking mechanism into your application.

Updates are key-based; there is no way to make atomic updates across keys. For example, you cannot make the update of one key dependent on the update of another key unless you design this functionality into your application.


The following table describes the characteristics of eventually consistent read and consistent read.

Eventually Consistent Read	Consistent Read
Stale reads possible	No stale reads
Lowest read latency	Potential higher read latency
Highest read throughput	Potential lower read throughput

Concurrent Applications


This section provides examples of eventually consistent and consistent read requests when multiple clients are writing to the same items.

In this example, both W1 (write 1) and W2 (write 2) complete before the start of R1 (read 1) and R2 (read 2). For a consistent read, R1 and R2 both return color = ruby. For an eventually consistent read, R1 and R2 might return color = red, color = ruby, or no results, depending on the amount of time that has elapsed.




In the next example, W2 does not complete before the start of R1. Therefore, R1 might return color = ruby or color = garnet for either a consistent read or an eventually consistent read. Also, depending on the amount of time that has elapsed, an eventually consistent read might return no results.

For a consistent read, R2 returns color = garnet. For an eventually consistent read, R2 might return color = ruby, color = garnet, or no results depending on the amount of time that has elapsed.



In the last example, Client 2 performs W2 before Amazon S3 returns a success for W1, so the outcome of the final value is unknown (color = garnet or color = brick). Any subsequent reads (consistent read or eventually consistent) might return either value. Also, depending on the amount of time that has elapsed, an eventually consistent read might return no results.



Features

Topics

- Reduced Redundancy Storage (p. 6)
- Bucket Policies (p. 7)
- AWS Identity and Access Management (p. 7)
- Access Control Lists (p. 7)
- Versioning (p. 8)
- Operations (p. 8)

This section describes important Amazon S3 features.

Reduced Redundancy Storage

Customers can store their data using the Amazon S3 Reduced Redundancy Storage (RRS) option. RRS enables customers to reduce their costs by storing non-critical, reproducible data at lower levels of redundancy than Amazon S3's standard storage. RRS provides a cost-effective, highly available solution for distributing or sharing content that is durably stored elsewhere, or for storing thumbnails, transcoded media, or other processed data that can be easily reproduced. The RRS option stores objects on multiple devices across multiple facilities, providing 400 times the durability of a typical disk drive, but does not replicate objects as many times as standard Amazon S3 storage, and thus is even more cost effective.

RRS provides 99.99% durability of objects over a given year. This durability level corresponds to an average expected loss of 0.01% of objects annually.

We charge less for using RRS than for standard Amazon S3 storage. For pricing information, go to the Amazon S3 detail page.

For more information, see Using Reduced Redundancy Storage (p. 260).

Bucket Policies

Bucket policies provide centralized, access control to buckets and objects based on a variety of conditions, including Amazon S3 operations, requesters, resources, and aspects of the request (e.g., IP address). The policies are expressed in our *access policy language* and enable centralized management of permissions. The permissions attached to a bucket apply to all of the objects in that bucket..

Individuals as well as companies can use bucket policies. When companies register with Amazon S3 they create an *account*. Thereafter, the company becomes synonymous with the account. Accounts are financially responsible for the Amazon resources they (and their employees) create. Accounts have the power to grant bucket policy permissions and assign employees permissions based on a variety of conditions. For example, an account could create a policy that gives a user write access:

- To a particular S3 bucket
- · From an account's corporate network
- · During business hours
- From an account's custom application (as identified by a user agent string)

An account can grant one application limited read and write access, but allow another to create and delete buckets as well. An account could allow several field offices to store their daily reports in a single bucket, allowing each office to write only to a certain set of names (e.g. "Nevada/*" or "Utah/*") and only from the office's IP address range.

Unlike ACLs (described below) that can only add (grant) permissions on individual objects, policies can either add or deny permissions across all (or a subset) of objects within a bucket. With one request an account can set the permissions of any number of objects in a bucket. An account can use wildcards (similar to regular expression operators) on Amazon resource names (ARNs) and other values, so that an account can control access to groups of objects that begin with a common prefix or end with a given extension such as .html.

Only the bucket owner is allowed to associate a policy with a bucket. Policies, written in the access policy language, *allow* or *deny* requests based on:

- Amazon S3 bucket operations (such as PUT ?acl), and object operations (such as PUT Object, or GET Object)
- Requester
- · Conditions specified in the policy

An account can control access based on specific Amazon S3 operations, such as GetObject, GetObjectVersion, DeleteObject, Or DeleteBucket.

The conditions can be such things as IP addresses, IP address ranges in CIDR notation, dates, user agents, HTTP referrer and transports (HTTP and HTTPS).

For more information, see Using Bucket Policies (p. 216).

AWS Identity and Access Management Access Control Lists

For more information, see Using ACLs (p. 228)

Versioning

For more information, see Object Versioning (p. 102)

Operations

Amazon S3 offers APIs in REST and SOAP. Following are the most common operations you'll execute through the API.

Common Operations

- Create a Bucket—Create and name your own bucket in which to store your objects.
- Write an Object—Store data by creating or overwriting an object.

 When you write an object, you specify a unique key in the namespace of your bucket. This is also a good time to specify any access control you want on the object.
- Read an Object—Read data back.
 You can choose to download the data via HTTP or BitTorrent.
- Deleting an Object—Delete some of your data.
- **Listing Keys**—List the keys contained in one of your buckets. You can filter the key list based on a prefix.

Details on this and all other functionality are described in detail later in this guide.

Amazon S3 Application Programming Interfaces (API)

The Amazon S3 architecture is designed to be programming language-neutral, using our supported interfaces to store and retrieve objects.

Amazon S3 provides a REST and a SOAP interface. They are similar, but there are some differences. For example, in the REST interface, metadata is returned in HTTP headers. Because we only support HTTP requests of up to 4 KB (not including the body), the amount of metadata you can supply is restricted.

The REST Interface

The REST API is an HTTP interface to Amazon S3. Using REST, you use standard HTTP requests to create, fetch, and delete buckets and objects.

You can use any toolkit that supports HTTP to use the REST API. You can even use a browser to fetch objects, as long as they are anonymously readable.

The REST API uses the standard HTTP headers and status codes, so that standard browsers and toolkits work as expected. In some areas, we have added functionality to HTTP (for example, we added headers to support access control). In these cases, we have done our best to add the new functionality in a way that matched the style of standard HTTP usage.

The SOAP Interface

The SOAP API provides a SOAP 1.1 interface using document literal encoding. The most common way to use SOAP is to download the WSDL (go to http://doc.s3.amazonaws.com/2006-03-01/AmazonS3.wsdl),

Amazon Simple Storage Service Developer Guide Paying for Amazon S3

use a SOAP toolkit such as Apache Axis or Microsoft .NET to create bindings, and then write code that uses the bindings to call Amazon S3.

Paying for Amazon S3

Pricing for Amazon S3 is designed so that you don't have to plan for the storage requirements of your application. Most storage providers force you to purchase a predetermined amount of storage and network transfer capacity: If you exceed that capacity, your service is shut off or you are charged high overage fees. If you do not exceed that capacity, you pay as though you used it all.

Amazon S3 charges you only for what you actually use, with no hidden fees and no overage charges. This gives developers a variable-cost service that can grow with their business while enjoying the cost advantages of Amazon's infrastructure.

Before storing anything in Amazon S3, you need to register with the service and provide a payment instrument that will be charged at the end of each month. There are no set-up fees to begin using the service. At the end of the month, your payment instrument is automatically charged for that month's usage.

For information about paying for Amazon S3 storage, go to the AWS Resource Center.

Related Amazon Web Services

Once we load your data into AWS you can use it with all AWS services. The following services are the ones you might use most frequently:

- Amazon ElasticCompute Cloud—This web service provides virtual compute resources in the cloud. For more information, go to Amazon ElasticCompute Cloud.
- Amazon Elastic MapReduce—This web service enables businesses, researchers, data analysts, and developers to easily and cost-effectively process vast amounts of data.
 It utilizes a hosted Hadoop framework running on the web-scale infrastructure of Amazon Elastic Compute Cloud (Amazon EC2) and Amazon Simple Storage Service (Amazon S3). For more information, go to Amazon Elastic MapReduce.
- Amazon Import/Export—This service enables you to mail a storage device, such as a RAID drive, to Amazon so that we can upload your (terabytes) of data onto Amazon S3. For more information, go to AWS Import/Export Developer Guide.

Making Requests

Topics

- Types of Security Credentials (p. 10)
- Viewing Your AWS Security Credentials (p. 12)
- Request Endpoints (p. 12)
- Making Requests using AWS SDKs (p. 13)
- Making Requests using the REST API (p. 45)

Amazon S3 is a REST service. You can send requests to Amazon S3 using the REST API or the AWS SDK (see STS Sample Code and Libraries), wrapper libraries that wrap the underlying Amazon S3 REST API simplifying your programming tasks.

Every interaction with Amazon S3 is either authenticated or anonymous. Authentication is a process of verifying the identify of the requester trying to access Amazon Web Services (AWS) product. Authenticated requests must include a signature value that authenticates the request sender. The signature value is, in part, generated from the requester's AWS security credentials.

If you are using the AWS SDK, the libraries compute the signature from the credentials you provide. However, if you make direct REST API calls in your application you must write the code to compute the signature and add it to the request.

Types of Security Credentials

The following sections review the types of security credentials that you can use to make authenticated requests.

AWS Account Security Credentials

When you create an AWS Account, AWS assigns the following credentials to you:

- Access Key ID (a 20-character, alphanumeric string). For example: 022QF06E7MXBSH9DHM02
- Secret Access Key (a 40-character string). For example: kWcrlUX5JEDGM/LtmEENI/aVmYvHNif5zB+d9+ct

Amazon Simple Storage Service Developer Guide IAM User Security Credentials

The Access Key ID uniquely identifies an AWS Account. You can use these AWS Account credentials to send authenticated requests to Amazon S3.

IAM User Security Credentials

You can create one AWS Account for your company, however, there may be several employees in the organization who need access to your organization's AWS resources. Sharing your AWS Account credentials reduces security, and creating individual AWS Accounts for each employee might not be practical. Also, you cannot easily share the resources such as buckets and objects because they are owned by different accounts. To share resources, you must grant permissions, which is additional work.

In such scenarios, you can use AWS Identity and Access Management (IAM) service to create users under your AWS Account with their own security credentials (Access Key ID and Secret Access Key) and attach IAM user policies granting appropriate resource access permissions to them. To better manage these users, IAM enables you to create groups of users and grant group level permissions that apply to all users in that group.

These users are referred as IAM users that you create and manage within AWS. The parent account controls a user's ability to access AWS. Any resources an IAM user creates are under the control of and paid for by the parent AWS Account. These IAM users can send authenticated requests to Amazon S3 using their own security credentials. For more information about creating and managing users under your AWS account, go to AWS Identity and Access Management (IAM).

Temporary Security Credentials

In addition to creating IAM users with their own security credentials, IAM also enables you to grant temporary security credentials to any user to enable them to access your AWS services and resources. You can manage users in AWS. These are referred as IAM users. You can also manage users in your system, outside AWS. These are referred as federated users. Additionally, users can also be applications that you create to access your AWS resources.

IAM provides the AWS Security Token Service API for you to request temporary security credentials. You can use either the AWS Security Token Service API or the AWS SDK to request these credentials. The API returns temporary security credentials (Access Key ID and Secret Access Key), and a security token. These credentials are valid at most for the duration you specify when you request them. You use the Access Key ID and Secret Access Key credentials the same way you use them when sending requests using your AWS Account or IAM user credentials. In addition, you must include the token in each request you send to Amazon S3.

An IAM user can request these temporary security credentials for their own use or hand them out to federated users or applications. When requesting temporary security credentials for federated users, you must provide a user name and an IAM policy defining the permissions you want to associate with these temporary security credentials. The federated user cannot get more permissions than the parent IAM user who requested the temporary credentials.

You can use these temporary security credentials in making requests to Amazon S3. The API libraries compute the necessary signature value using those credentials to authenticate your request. If you send requests using expired credentials, Amazon S3 denies the request.

For information on signing requests using temporary security credentials in your REST API requests, see Signing and Authenticating REST Requests (p. 48). For information about sending requests using AWS SDKs, see Making Requests using AWS SDKs (p. 13).

For more information about IAM support for temporary security credentials, go to Granting Temporary Access to Your AWS Resources.

Viewing Your AWS Security Credentials

AWS Accounts and IAM users have Access Key ID and Secret Access Key security credentials.

Viewing Your AWS Account Security Credentials

Your Access Key ID and Secret Access Key are displayed when you create your AWS account. They are not e-mailed to you. If you need to see them again, you can view them at any time from your AWS account.

- 1. Go to the Amazon Web Services web site at http://aws.amazon.com.
- 2. Click the Account tab.
- Click Security Credentials.
 If you have not already signed in, Sign In or Create an AWS Account page displays. You must sign in before you can see your AWS account security credentials.

Your access credentials, Access Key ID and Secret Access Key, are displayed on the resulting Security Credentials page.

Viewing Your IAM User Security Credentials

An AWS Account owner creates IAM users under its account. When the owner creates an IAM user under its account, the account owner gets to download the IAM user credentials (Access Key ID and Secret Access Key). The account owner can then provide these credentials for others to use. The IAM user can then use these credentials to send requests to Amazon S3.

Each IAM user needs a password to connect to the AWS Management Console. For more information, go to How does a user sign in?.

Viewing Your Temporary Security Credentials

You request temporary security credentials programmatically. You can view them only when they are created.

Request Endpoints

You send REST requests to the service's predefined endpoint. The *Amazon Web Services General Reference* lists AWS Services and the corresponding endpoints. For information about Amazon S3 regions and endpoints, go to Regions and Endpoints.

Making Requests using AWS SDKs

Topics

- Making Requests Using AWS Account or IAM User Credentials (p. 14)
- Making Requests Using IAM User Temporary Credentials (p. 18)
- Making Requests Using Federated User Temporary Credentials (p. 29)

You can send authenticated requests to Amazon S3 using either the AWS SDK or by making the REST API calls directly in your application. The AWS SDK API uses the credentials that you provide to compute the signature for authentication. If you use the REST API directly in your applications, you must write the necessary code to compute the signature for authenticating your request.

Making Requests Using AWS Account or IAM User Credentials

Topics

- Making Requests Using AWS Account or IAM User Credentials AWS SDK for Java (p. 14)
- Making Requests Using AWS Account or IAM User Credentials AWS SDK for .NET (p. 15)
- Making Requests Using AWS Account or IAM User Credentials AWS SDK for PHP (p. 15)
- Making Requests Using AWS Account or IAM User Credentials AWS SDK for Ruby (p. 17)

You can use an AWS Account or IAM user security credentials to send authenticated requests to Amazon S3. This section provides examples of how you can send authenticated requests using the AWS SDK for Java, .NET, and PHP.

Making Requests Using AWS Account or IAM User Credentials - AWS SDK for Java

The following tasks guide you through using the Java classes to send authenticated requests using your AWS Account credentials or IAM user credentials.

Making Requests Using Your AWS Account or IAM user Credentials

1	Create an instance of the AmazonS3Client class by providing your AWS Account or IAM user credentials (Access Key ID, Secret Access Key).
2	Execute one of the AmazonS3Client methods to send requests to Amazon S3. The client generates the necessary signature value from your credentials and includes it in the request it sends to Amazon S3.

The following Java code sample demonstrates the preceding tasks.



Note

You can create the AmazonS3Client client without providing your security credentials. Requests sent using this client are anonymous requests, without a signature. Amazon S3 returns an error if you send anonymous requests for a resource that is not publicly available.

For working examples, see Working with Amazon S3 Objects (p. 100) and Working with Amazon S3 Buckets (p. 82). You can test these examples using your AWS Account or IAM user credentials.

For example, to list all the object keys in your bucket, see Listing Keys Using the AWS SDK for Java (p. 195).

Related Resources

• Using the AWS SDKs and Explorers (p. 325)

Making Requests Using AWS Account or IAM User Credentials - AWS SDK for .NET

The following tasks guide you through using the .NET classes to send authenticated requests using your AWS account or IAM user credentials.

Making Requests Using Your AWS Account or IAM user Credentials

1	Create an instance of the Amazons3Client class by providing your AWS Account or IAM user credentials (Access Key ID, Secret Access Key).	
2	Execute one of the AmazonS3Client methods to send requests to Amazon S3. The client generates the necessary signature from your credentials and includes it in the request it sends to Amazon S3.	

The following C# code sample demonstrates the preceding tasks.



Note

You can create the AmazonS3Client client without providing your security credentials. Requests sent using this client are anonymous requests, without a signature. Amazon S3 returns an error if you send anonymous requests for a resource that is not publicly available.

For working examples, see Working with Amazon S3 Objects (p. 100) and Working with Amazon S3 Buckets (p. 82). You can test these examples using your AWS Account or an IAM user credentials.

For example, to list all the object keys in your bucket, see Listing Keys Using the AWS SDK for .NET (p. 198).

Related Resources

• Using the AWS SDKs and Explorers (p. 325)

Making Requests Using AWS Account or IAM User Credentials - AWS SDK for PHP

The following tasks guide you through using the PHP classes to send authenticated requests using your AWS account or IAM user credentials.

Amazon Simple Storage Service Developer Guide Making Requests Using AWS Account or IAM User Credentials

Making Requests Using Your AWS Account or IAM user Credentials

1	Create an instance of the AmazonS3 class by providing your AWS Account or IAM user credentials.
2	Execute one of the AmazonS3 methods to send requests to Amazon S3. The client API generates the necessary signature from your credentials and include it in the request it sends to Amazon S3.

The following PHP code sample demonstrates the preceding tasks and illustrate how the AmazonS3 client sends a request to list all object keys in a bucket.

```
// Instantiate the class.
$s3 = new AmazonS3();
// Use the high-level API.
$response = $s3->get_object_list($bucket);
```



Note

You can create the AmazonS3 client without providing your security credentials. Requests sent using this client are anonymous requests, without a signature. Amazon S3 returns an error if you send anonymous requests for a resource that is not publicly available.

For working examples, see Working with Amazon S3 Objects (p. 100) and Working with Amazon S3 Buckets (p. 82). You can test these examples using your AWS Account or IAM user credentials.

For example, to list all the object keys in your bucket, see Listing Keys Using the AWS SDK for PHP (p. 202).

Related Resources

• Using the AWS SDKs and Explorers (p. 325)

Making Requests Using AWS Account or IAM User Credentials - AWS SDK for Ruby

The following tasks guide you through using the AWS SDK for Ruby to send authenticated requests using your AWS Account credentials or IAM user credentials.

Making Requests Using Your AWS Account or IAM user Credentials

1	Create an instance of the AWS:: S3 class by providing your AWS Account or IAM user credentials (Access Key ID, Secret Access Key).
2	Make a request to Amazon S3 by enumerating objects in a bucket using the buckets method of AWS::S3. The client generates the necessary signature value from your credentials and includes it in the request it sends to Amazon S3.

The following Ruby code sample demonstrates the preceding tasks.

```
# Get an instance of the S3 interface using the specified credentials configur
ation.
s3 = AWS::S3.new(
    :access_key_id => my_access_key_id,
    :secret_access_key => my_secret_key)

# Get a list of all object keys in a bucket.
bucket = s3.buckets[bucket_name].objects.collect(&:key)
puts bucket
```



Note

You can create the AWS:S3 client without providing your security credentials. Requests sent using this client are anonymous requests, without a signature. Amazon S3 returns an error if you send anonymous requests for a resource that is not publicly available.

For working examples, see Working with Amazon S3 Objects (p. 100) and Working with Amazon S3 Buckets (p. 82). You can test these examples using your AWS Account or IAM user credentials.

Making Requests Using IAM User Temporary Credentials

Topics

- Making Requests Using IAM User Temporary Credentials AWS SDK for Java (p. 18)
- Making Requests Using IAM User Temporary Credentials AWS SDK for .NET (p. 21)
- Making Requests Using IAM User Temporary Credentials AWS SDK for PHP (p. 24)
- · Making Requests Using IAM User Temporary Credentials AWS SDK for Ruby (p. 27)

An AWS Account or an IAM user can request temporary security credentials and use them to send authenticated requests to Amazon S3. This section provides examples of how to use the AWS SDK for Java, .NET, and PHP to obtain temporary security credentials and use them to authenticate your requests to Amazon S3.

Making Requests Using IAM User Temporary Credentials - AWS SDK for Java

An IAM user or an AWS Account can request temporary security credentials (see Making Requests (p. 10)) using AWS SDK for Java and use them to access Amazon S3. These credentials expire after the session duration. By default, the session duration is one hour. If you use IAM user credentials, you can specify duration, between 1 and 36 hours, when requesting the temporary security credentials.

Making Requests Using IAM User Temporary Security Credentials

1	Create an instance of the AWS Security Token Service client AWSSecurityTokenServiceClient by providing your credentials.
2	Start a session by calling the GetSessionToken method of the STS client you created in the preceding step. You provide session information to this method using a GetSessionTokenRequest object.
	The method returns your temporary security credentials.
3	Package the temporary security credentials in an instance of the BasicSessionCredentials object so you can provide the credentials to your Amazon S3 client.
4	Create an instance of the Amazons3Client class by passing in the temporary security credentials. You send the requests to Amazon S3 using this client. If you send requests using expired credentials, Amazon S3 returns an error.

The following Java code sample demonstrates the preceding tasks.

Amazon Simple Storage Service Developer Guide Making Requests Using IAM User Temporary Credentials

```
//
// Manually start a session.
GetSessionTokenRequest getSessionTokenRequest = new GetSessionTokenRequest();
// Following duration can be set only if temporary credentials are requested
getSessionTokenRequest.setDurationSeconds(7200);
GetSessionTokenResult sessionTokenResult =
                           stsClient.getSessionToken(getSessionTokenRequest);
Credentials sessionCredentials = sessionTokenResult.getCredentials();
// Package the temporary security credentials as
// a BasicSessionCredentials object, for an Amazon S3 client object to use.
BasicSessionCredentials basicSessionCredentials =
              new BasicSessionCredentials(sessionCredentials.getAccessKeyId(),
                                     sessionCredentials.getSecretAccessKey(),
                                      sessionCredentials.getSessionToken());
// The following will be part of your less trusted code. You provide temporary
security
// credentials so it can send authenticated requests to Amazon S3.
// Create Amazon S3 client by passing in the basicSessionCredentials object.
AmazonS3Client s3 = new AmazonS3Client(basicSessionCredentials);
// Test. For example, get object keys in a bucket.
ObjectListing objects = s3.listObjects(bucketName);
```

Example



Note

If you obtain temporary security credentials using your AWS account credentials, the temporary security credentials are valid for only one hour. You can specify session duration only if you use IAM user credentials to request a session.

The following Java code example lists the object keys in the specified bucket. For illustration, the code example obtains temporary security credentials for a default one hour session and uses them to send an authenticated request to Amazon S3.

If you want to test the sample using IAM user credentials, you will need to create an IAM user under your AWS Account. For more information about how to create an IAM user, go to Set Up a Group, Grant Permissions, and Add Users in the AWS Identity and Access Management Getting Started Guide.

```
import java.io.IOException;
import com.amazonaws.auth.BasicSessionCredentials;
import com.amazonaws.auth.PropertiesCredentials;
import com.amazonaws.services.s3.AmazonS3Client;
import com.amazonaws.services.securitytoken.AWSSecurityTokenServiceClient;
import com.amazonaws.services.securitytoken.model.Credentials;
import com.amazonaws.services.securitytoken.model.GetSessionTokenRequest;
import com.amazonaws.services.securitytoken.model.GetSessionTokenResult;
import com.amazonaws.services.s3.model.ObjectListing;
public class S3Sample {
private static String bucketName = "*** Provide bucket name ***";
    public static void main(String[] args) throws IOException {
          PropertiesCredentials credentials = new PropertiesCredentials(
            S3Sample.class.getResourceAsStream("AwsCredentials.properties"));
        AWSSecurityTokenServiceClient stsClient =
                               new AWSSecurityTokenServiceClient(credentials);
        //
        // Start a session.
        GetSessionTokenRequest getSessionTokenRequest =
                                             new GetSessionTokenRequest();
        GetSessionTokenResult sessionTokenResult =
                            stsClient.getSessionToken(getSessionTokenRequest);
        Credentials sessionCredentials = sessionTokenResult.getCredentials();
        System.out.println("Session Credentials: "
                                             + sessionCredentials.toString());
        // Package the session credentials as a BasicSessionCredentials
        // object for an S3 client object to use.
        BasicSessionCredentials basicSessionCredentials =
            new BasicSessionCredentials(sessionCredentials.getAccessKeyId(),
```

Amazon Simple Storage Service Developer Guide Making Requests Using IAM User Temporary Credentials

Related Resources

• Using the AWS SDKs and Explorers (p. 325)

Making Requests Using IAM User Temporary Credentials - AWS SDK for .NET

An IAM user or an AWS Account can request temporary security credentials (see Making Requests (p. 10)) using AWS SDK for .NET and use them to access Amazon S3. These credentials expire after the session duration. By default, the session duration is one hour. If you use IAM user credentials, you can specify duration, between 1 and 36 hours, when requesting the temporary security credentials.

Making Requests Using IAM User Temporary Security Credentials

1	Create an instance of the AWS Security Token Service client AmazonSecurityTokenServiceClient by providing your credentials.
2	Start a session by calling the GetSessionToken method of the STS client you created in the preceding step. You provide session information to this method using a GetSessionTokenRequest object.
	The method returns you temporary security credentials.
3	Package up the temporary security credentials in an instance of the SessionAWSCredentials object. You use this object to provide the temporary security credentials to your Amazon S3 client.
4	Create an instance of the Amazons3Client class by passing in the temporary security credentials.
	You send requests to Amazon S3 using this client. If you send requests using expired credentials, Amazon S3 returns an error.

The following C# code sample demonstrates the preceding tasks.

Amazon Simple Storage Service Developer Guide Making Requests Using IAM User Temporary Credentials

```
config);
GetSessionTokenRequest getSessionTokenRequest = new GetSessionTokenRequest();
// Following duration can be set only if temporary credentials are requested
by an IAM user.
getSessionTokenRequest.DurationSeconds = 7200; // seconds.
Credentials credentials =
    stsClient.GetSessionToken(getSessionTokenRequest).GetSessionTokenResult.Cre
dentials;
SessionAWSCredentials sessionCredentials =
                          new SessionAWSCredentials(credentials.AccessKeyId,
                                                  credentials.SecretAccessKey,
                                                    credentials.SessionToken);
// The following will be part of your less trusted code. You provide temporary
security
// credentials so it can send authenticated requests to Amazon S3.
// Create Amazon S3 client by passing in the basicSessionCredentials object.
AmazonS3Client s3Client = new AmazonS3Client(sessionCredentials);
// Test. For example, send request to list object key in a bucket.
var response = s3Client.ListObjects(bucketName);
```

Example



Note

If you obtain temporary security credentials using your AWS account credentials, the temporary security credentials are valid for only one hour. You can specify session duration only if you use IAM user credentials to request a session.

The following C# code example lists object keys in the specified bucket. For illustration, the code example obtains temporary security credentials for a default one hour session and uses them to send authenticated request to Amazon S3.

If you want to test the sample using IAM user credentials, you will need to create an IAM user under your AWS Account. For more information about how to create an IAM user, go to Set Up a Group, Grant Permissions, and Add Users in the AWS Identity and Access Management Getting Started Guide.

```
using System;
using System.Configuration;
using System.Collections.Specialized;
using Amazon.S3;
using Amazon.SecurityToken;
using Amazon.SecurityToken.Model;
using Amazon.Runtime;
using Amazon.S3.Model;
using System.Collections.Generic;
namespace s3.amazon.com.docsamples.listingkeys
   class TempCred_ExplicitSessionStart
       static string bucketName = "*** Provide bucket name ***";
       static AmazonS3 client;
        public static void Main(string[] args)
            NameValueCollection appConfig = ConfigurationManager.AppSettings;
            string accessKeyID = appConfig["AWSAccessKey"];
            string secretAccessKeyID = appConfig["AWSSecretKey"];
            try
                Console.WriteLine("Listing objects stored in a bucket");
                SessionAWSCredentials tempCredentials =
                     GetTemporaryCredentials(accessKeyID, secretAccessKeyID);
                // Create client by providing temporary security credentials.
                AmazonS3Client s3Client = new AmazonS3Client(tempCredentials);
                ListObjectsRequest listObjectRequest =
                                  new ListObjectsRequest();
                listObjectRequest.BucketName = bucketName;
                // Send request to Amazon S3.
             ListObjectsResponse response = s3Client.ListObjects(listObjectRe
quest);
                List<S3Object> objects = response.S3Objects;
                Console.WriteLine("Object count = {0}", objects.Count);
```

```
Console.WriteLine("Press any key to continue...");
                                 Console.ReadKey();
                      catch (AmazonS3Exception s3Exception)
                                  Console.WriteLine(s3Exception.Message,
                                                                                    s3Exception.InnerException);
                      catch (AmazonSecurityTokenServiceException stsException)
                                  Console.WriteLine(stsException.Message,
                                                                                 stsException.InnerException);
           }
           private static SessionAWSCredentials GetTemporaryCredentials(
                                                           string accessKeyId, string secretAccessKeyId)
                      AmazonSecurityTokenServiceClient stsClient =
                                 new AmazonSecurityTokenServiceClient(accessKeyId,
                                                                                                                                          secretAccessKeyId);
                      GetSessionTokenRequest getSessionTokenRequest =
                                                                                                                   new GetSessionTokenRequest();
                      getSessionTokenRequest.DurationSeconds = 7200; // seconds
                      GetSessionTokenResponse sessionTokenResponse =
                                                             stsClient.GetSessionToken(getSessionTokenRequest);
                      GetSessionTokenResult sessionTokenResult =
                                                                                      sessionTokenResponse.GetSessionTokenResult;
                      Credentials credentials = sessionTokenResult.Credentials;
                      SessionAWSCredentials sessionCredentials =
        {\tt SessionAWSCredentials.CreateStaticCredentials(credentials.AccessKeyId, and the accessKeyId, and the accessKeyId, are accessfied and the accession acc
                                                                                                                                 credentials.SecretAccessKey,
                                                                                                                                       credentials.SessionToken);
                      return sessionCredentials;
}
```

Related Resources

• Using the AWS SDKs and Explorers (p. 325)

Making Requests Using IAM User Temporary Credentials - AWS SDK for PHP

An IAM user or an AWS Account can request temporary security credentials (see Making Requests (p. 10)) using the AWS SDK for PHP and use them to access Amazon S3. These credentials expire after the

Amazon Simple Storage Service Developer Guide Making Requests Using IAM User Temporary Credentials

session duration. By default, the session duration is one hour. If you use IAM user credentials, you can specify the duration, between 1 and 36 hours, when requesting the temporary security credentials.

Making Requests Using IAM User Temporary Security Credentials

1	Create an instance of the AmazonSTS class by providing your credentials.
2	Execute the AmazonSTS::get_session_token() method to start a session. The method returns you temporary security credentials.
3	Create an instance of the AmazonS3 class by providing the temporary security credentials you obtained in the preceding step.
	Any methods in the ${\tt AmazonS3}$ class that you call use the temporary security credentials to send authenticated requests to Amazon S3.

The following PHP code sample demonstrates the preceding tasks.

```
// In real applications, the following code is part of your trusted code. It
has
// your security credentials that you use to obtain temporary security creden
tials.
$token = new AmazonSTS();
$response = $token->get_session_token();
$AccessKeyId = (string)$response->body->GetSessionTokenResult->Credentials-
>AccessKeyId;
$SecretAccessKey = (string)$response->body->GetSessionTokenResult->Credentials-
>SecretAccessKey;
$SessionToken = (string)$response->body->GetSessionTokenResult->Credentials-
>SessionToken;
// The following will be part of your less trusted code. You provide temporary
security
// credentials so it can send authenticated requests to Amazon S3.
// Create an AmazonS3 using temporary security credentials.
$s3 = new AmazonS3($AccessKeyId, $SecretAccessKey, $SessionToken);
// Send requests to Amazon S3.
```



Note

If you obtain temporary security credentials using your AWS account credentials, the temporary security credentials are valid for only one hour. You can specify the session duration only if you use IAM user credentials to request a session.

Example

The following PHP code example lists object keys in the specified bucket. For illustration, the code example obtains temporary security credentials for a default one hour session and uses them to send authenticated request to Amazon S3.

If you want to test the sample using IAM user credentials, you will need to create an IAM user under your AWS Account. For more information about how to create an IAM user, go to Set Up a Group, Grant Permissions, and Add Users in the AWS Identity and Access Management Getting Started Guide.

```
<?php
require_once '../aws-sdk-for-php/sdk.class.php';
header('Content-Type: text/plain; charset=utf-8');
$bucket = '*** Provide bucket name ***';
$token = new AmazonSTS();
$response1 = $token->get_session_token();
$AccessKeyId = (string)$response1->body->GetSessionTokenResult->Credentials-
>AccessKeyId;
$SecretAccessKey = (string)$response1->body->GetSessionTokenResult->Credentials-
>SecretAccessKey;
$SessionToken = (string)$response1->body->GetSessionTokenResult->Credentials-
>SessionToken;
// Instantiate the class.
$s3 = new AmazonS3($AccessKeyId, $SecretAccessKey, $SessionToken);
// Send list object request.
$response = $s3->list_objects($bucket);
// Success?
print_r(gettype($response) === 'array');
if($response)
{
   echo "Keys retrieved!" . PHP_EOL;
 foreach ($response as $key)
        print_r($key);
}
else
    print_r($response);
```

Related Resources

Using the AWS SDKs and Explorers (p. 325)

Making Requests Using IAM User Temporary Credentials - AWS SDK for Ruby

An IAM user or an AWS Account can request temporary security credentials (see Making Requests (p. 10)) using AWS SDK for Ruby and use them to access Amazon S3. These credentials expire after the session duration. By default, the session duration is one hour. If you use IAM user credentials, you can specify the duration, between 1 and 36 hours, when requesting the temporary security credentials.

Making Requests Using IAM User Temporary Security Credentials

1	Create an instance of the AWS Security Token Service client AWS::STS::Session by providing your credentials.
2	Start a session by calling the new_session method of the STS client that you created in the preceding step. You provide session information to this method using a GetSessionTokenRequest object.
	The method returns your temporary security credentials.

The following Ruby code sample demonstrates the preceding tasks.

```
# Start a session.
# In real applications, the following code is part of your trusted code. It has
# your security credentials that you use to obtain temporary security creden
tials.

sts = AWS::STS.new(
    :access_key_id => my_access_key_id,
    :secret_access_key => my_secret_key)

session = sts.new_session()
puts "Session expires at: #{session.expires_at.to_s}"

# Get an instance of the S3 interface using the session credentials.
s3 = AWS::S3.new(session.credentials)

# Get a list of all object keys in a bucket.
bucket = s3.buckets[bucket_name].objects.collect(&:key)
```

Example



Note

If you obtain temporary security credentials using your AWS account credentials, the temporary security credentials are valid for only one hour. You can specify session duration only if you use IAM user credentials to request a session.

The following Ruby code example lists the object keys in the specified bucket. For illustration, the code example obtains temporary security credentials for a default one hour session and uses them to send an authenticated request to Amazon S3.

If you want to test the sample using IAM user credentials, you will need to create an IAM user under your AWS Account. For more information about how to create an IAM user, go to Set Up a Group, Grant Permissions, and Add Users in the AWS Identity and Access Management Getting Started Guide.

```
require 'rubygems'
require 'aws-sdk'
# In real applications, the following code is part of your trusted code. It has
# your security credentials you use to obtain temporary security credentials.
my_access_key_id = '***Provide Access Key ID***'
my_secret_key = '***Provide Secret Key***'
bucket_name = '*** Provide bucket name ***'
AWS.config({
  :access_key_id => my_access_key_id,
  :secret_access_key => my_secret_key
})
# Start a session.
sts = AWS::STS.new()
session = sts.new_session()
puts "Session expires at: #{session.expires_at.to_s}"
# get an instance of the S3 interface using the session credentials
s3 = AWS::S3.new(session.credentials)
# get a list of all object keys in a bucket
bucket = s3.buckets[bucket_name].objects.collect(&:key)
puts bucket
```

Making Requests Using Federated User Temporary Credentials

Topics

- Making Requests Using Federated User Temporary Credentials AWS SDK for Java (p. 29)
- Making Requests Using Federated User Temporary Credentials AWS SDK for .NET (p. 34)
- Making Requests Using Federated User Temporary Credentials AWS SDK for PHP (p. 38)
- Making Requests Using Federated User Temporary Credentials AWS SDK for Ruby (p. 43)

You can request temporary security credentials and provide them to your federated users or applications who need to access your AWS resources. This section provides examples of how you can use the AWS SDK to obtain temporary security credentials for your federated users or applications and send authenticated requests to Amazon S3 using those credentials.



Note

Both the AWS account and an IAM user can request temporary security credentials for federated users. However, for added security, only an IAM user with the necessary permissions should request these temporary credentials to ensure that the federated user gets at most the permissions of the requesting IAM user. In some applications, you might find suitable to create an IAM user with specific permissions for the sole purpose of granting temporary security credentials to your federated users and applications.

Making Requests Using Federated User Temporary Credentials - AWS SDK for Java

You can provide temporary security credentials for your federated users and applications (see Making Requests (p. 10)) so they can send authenticated requests to access your AWS resources. When requesting these temporary credentials from the IAM service, you must provide a user name and an IAM policy describing the resource permissions you want to grant. By default, the session duration is one hour. However, if you are requesting temporary credentials using IAM user credentials, you can explicitly set a different duration value when requesting the temporary security credentials for federated users and applications.



Note

To request temporary security credentials for federated users and applications, for added security, you might want to use a dedicated IAM user with only the necessary access permissions . The temporary user you create can never get more permissions than the IAM user who requested the temporary security credentials. For more information, go to AWS Identity and Access Management FAQs

Making Requests Using Federated User Temporary Security Credentials

1 Create an instance of the AWS Security Token Service client
AWSSecurityTokenServiceClient by providing your security credentials.

2	Start a session by calling the getFederationToken method of the STS client you created in the preceding step. You will need to provide session information including the user name and an IAM policy that you want to attach to the temporary credentials. This method returns your temporary security credentials.
3	Package the temporary security credentials in an instance of the BasicSessionCredentials object. You use this object to provide the temporary security credentials to your Amazon S3 client.
4	Create an instance of the AmazonS3Client class by passing the temporary security credentials. You send requests to Amazon S3 using this client. If you send requests using expired credentials, Amazon S3 returns an error.

The following Java code sample demonstrates the preceding tasks.

```
// In real applications, the following code is part of your trusted code. It
has
// your security credentials you use to obtain temporary security credentials.
AWSCredentials credentials =
          new BasicAWSCredentials("*** Access Key ID ***",
                                  "*** Secret Key ***");
AWSSecurityTokenServiceClient stsClient =
                       new AWSSecurityTokenServiceClient(credentials);
GetFederationTokenRequest getFederationTokenRequest =
                        new GetFederationTokenRequest();
getFederationTokenRequest.setDurationSeconds(7200);
getFederationTokenRequest.setName("User1");
// Define the policy and add to the request.
Policy policy = new Policy();
// Define the policy here.
// Add the policy to the request.
getFederationTokenRequest.setPolicy(policy.toJson());
GetFederationTokenResult federationTokenResult =
                     stsClient.getFederationToken(getFederationTokenRequest);
Credentials sessionCredentials = federationTokenResult.getCredentials();
// Package the session credentials as a BasicSessionCredentials object
// for an S3 client object to use.
BasicSessionCredentials basicSessionCredentials = new BasicSessionCredentials(
      sessionCredentials.getAccessKeyId(),
      sessionCredentials.getSecretAccessKey(),
      sessionCredentials.getSessionToken());
// The following will be part of your less trusted code. You provide temporary
security
// credentials so it can send authenticated requests to Amazon S3.
// Create an Amazon S3 client by passing in the basicSessionCredentials object.
AmazonS3Client s3 = new AmazonS3Client(basicSessionCredentials);
```

// Test. For example, send list object keys in a bucket.
ObjectListing objects = s3.listObjects(bucketName);

Example

The following Java code example lists keys in the specified bucket. In the code example, you first obtain temporary security credentials for a two hour session for your federated user (User1) and use them to send authenticated requests to Amazon S3.

When requesting temporary credentials for others, for added security, you use the security credentials of an IAM user who has permissions to request temporary security credentials. You can also limit the access permissions of this IAM user to ensure that the IAM user grants only the minimum application specific permissions when requesting temporary security credentials. This sample only lists objects in a specific bucket. Therefore, first create an IAM user with the following policy attached.

The policy allows the IAM user to request temporary security credentials and access permission to only list your AWS resources. For more information about how to create an IAM user, go to Set Up a Group, Grant Permissions, and Add Users in the AWS Identity and Access Management Getting Started Guide.

You can now use the IAM user security credentials to test the following example. The example sends authenticated request to Amazon S3 using temporary security credentials. The example specifies the following policy when requesting temporary security credentials for the federated user (User1) which restricts access to list objects in a specific bucket (YourBucketName). You must update the policy and provide your own existing bucket name.

You must update the following sample and provide the bucket name that you specified in the preceding federated user access policy.

```
import java.io.IOException;
import com.amazonaws.auth.BasicSessionCredentials;
import com.amazonaws.auth.PropertiesCredentials;
import com.amazonaws.auth.policy.Policy;
import com.amazonaws.auth.policy.Resource;
import com.amazonaws.auth.policy.Statement;
import com.amazonaws.auth.policy.Statement.Effect;
import com.amazonaws.auth.policy.actions.S3Actions;
import com.amazonaws.services.s3.AmazonS3Client;
```

```
import com.amazonaws.services.securitytoken.AWSSecurityTokenServiceClient;
import com.amazonaws.services.securitytoken.model.Credentials;
import com.amazonaws.services.securitytoken.model.GetFederationTokenRequest;
import com.amazonaws.services.securitytoken.model.GetFederationTokenResult;
import com.amazonaws.services.s3.model.ObjectListing;
public class S3Sample {
private static String bucketName = "*** Specify bucket name ***";
   public static void main(String[] args) throws IOException {
        PropertiesCredentials credentials = new PropertiesCredentials(
             S3Sample.class.getResourceAsStream("AwsCredentials.properties"));
        AWSSecurityTokenServiceClient stsClient =
                        new AWSSecurityTokenServiceClient(credentials);
        GetFederationTokenRequest getFederationTokenRequest =
                                         new GetFederationTokenRequest();
        getFederationTokenRequest.setDurationSeconds(7200);
        getFederationTokenRequest.setName("User1");
        // Define the policy and add to the request.
        Policy policy = new Policy();
        policy.withStatements(new Statement(Effect.Allow)
            .withActions(S3Actions.ListObjects)
            .withResources(new Resource("arn:aws:s3:::ExampleBucket")));
        getFederationTokenRequest.setPolicy(policy.toJson());
        // Get the temporary security credentials.
        GetFederationTokenResult federationTokenResult =
                     stsClient.getFederationToken(getFederationTokenRequest);
      Credentials sessionCredentials = federationTokenResult.getCredentials();
        // Package the session credentials as a BasicSessionCredentials
        // object for an S3 client object to use.
        BasicSessionCredentials basicSessionCredentials =
             new BasicSessionCredentials(sessionCredentials.getAccessKeyId(),
                                    sessionCredentials.getSecretAccessKey(),
                                    sessionCredentials.getSessionToken());
       AmazonS3Client s3 = new AmazonS3Client(basicSessionCredentials);
       // Test. For example, send ListBucket request using the temporary secur
ity credentials.
       ObjectListing objects = s3.listObjects(bucketName);
        System.out.println("No. of Objects = " + objects.getObjectSummar
ies().size());
```

Related Resources

Using the AWS SDKs and Explorers (p. 325)

Making Requests Using Federated User Temporary Credentials - AWS SDK for .NET

You can provide temporary security credentials for your federated users and applications (see Making Requests (p. 10)) so they can send authenticated requests to access your AWS resources. When requesting these temporary credentials, you must provide a user name and an IAM policy describing the resource permissions you want to grant. By default, the session duration is one hour. You can explicitly set a different duration value when requesting the temporary security credentials for federated users and applications.



Note

To request temporary security credentials for federated users and applications, for added security, you might want to use a dedicated IAM user with only the necessary access permissions. The temporary user you create can never get more permissions than the IAM user who requested the temporary security credentials. For more information, go to AWS Identity and Access Management FAQs

Making Requests Using Federated User Temporary Credentials

1	Create an instance of the AWS Security Token Service client, AmazonSecurityTokenServiceClient class, by providing your credentials.
2	Start a session by calling the GetFederationToken method of the STS client. You will need to provide session information including the user name and an IAM policy that you want to attach to the temporary credentials. You can provide an optional session duration. This method returns your temporary security credentials.
3	Package the temporary security credentials in an instance of the SessionAWSCredentials object. You use this object to provide the temporary security credentials to your Amazon S3 client.
4	Create an instance of the AmazonS3Client class by passing the temporary security credentials. You send requests to Amazon S3 using this client. If you send requests using expired credentials, Amazon S3 returns an error.

The following C# code sample demonstrates the preceding tasks.

```
GetFederationTokenResponse federationTokenResponse =
                  stsClient.GetFederationToken(federationTokenRequest);
GetFederationTokenResult federationTokenResult =
                  federationTokenResponse.GetFederationTokenResult;
Credentials credentials = federationTokenResult.Credentials;
SessionAWSCredentials sessionCredentials =
                new SessionAWSCredentials(credentials.AccessKeyId,
                                          credentials.SecretAccessKey,
                                          credentials.SessionToken);
// The following will be part of your less trusted code. You provide temporary
security
// credentials so it can send authenticated requests to Amazon S3.
// Create Amazon S3 client by passing in the basicSessionCredentials object.
AmazonS3Client s3Client = new AmazonS3Client(sessionCredentials);
// Test. For example, send list object keys in a bucket.
ListObjectsRequest listObjectRequest = new ListObjectsRequest();
listObjectRequest.BucketName = bucketName;
ListObjectsResponse response = s3Client.ListObjects(listObjectRequest);
```

Example

The following C# code example lists keys in the specified bucket. In the code example, you first obtain temporary security credentials for a two hour session for your federated user (User1) and use them to send authenticated requests to Amazon S3.

When requesting temporary credentials for others, for added security, you use the security credentials of an IAM user who has permissions to request temporary security credentials. You can also limit the access permissions of this IAM user to ensure that the IAM user grants only the minimum application specific permissions to the federated user. This sample only lists objects in a specific bucket. Therefore, first create an IAM user with the following policy attached.

The policy allows the IAM user to request temporary security credentials and access permission to only list your AWS resources. For more information about how to create an IAM user, go to Set Up a Group, Grant Permissions, and Add Users in the AWS Identity and Access Management Getting Started Guide.

You can now use the IAM user security credentials to test the following example. The example sends authenticated request to Amazon S3 using temporary security credentials. The example specifies the following policy when requesting temporary security credentials for the federated user (User1) which restricts access to list objects in a specific bucket (YourBucketName). You must update the policy and provide your own existing bucket name.

```
{
   "Statement":[
      {
        "Sid":"1",
        "Action":["s3:ListBucket"],
        "Effect":"Allow",
        "Resource":"arn:aws:s3:::YourBucketName"
   }
}
```

You must update the following sample and provide the bucket name that you specified in the preceding federated user access policy.

```
using System;
using System.Configuration;
using System.Collections.Specialized;
using Amazon.S3;
using Amazon.SecurityToken;
using Amazon.SecurityToken.Model;
using Amazon.Runtime;
using Amazon.S3.Model;
using System.Collections.Generic;
```

```
namespace s3.amazon.com.docsamples.listingkeys
    class TempCred_FederatedCredentials
        static string bucketName = "*** Provide bucket name ***";
       public static void Main(string[] args)
            NameValueCollection appConfig = ConfigurationManager.AppSettings;
            string accessKeyID = appConfig["AWSAccessKey"];
            string secretAccessKeyID = appConfig["AWSSecretKey"];
            try
                Console.WriteLine("Listing objects stored in a bucket");
                SessionAWSCredentials tempCredentials =
                     GetTemporaryFederatedCredentials(accessKeyID,
                                                      secretAccessKeyID);
                AmazonS3Client s3Client = new AmazonS3Client(tempCredentials);
                ListObjectsRequest listObjectRequest =
                                  new ListObjectsRequest();
                listObjectRequest.BucketName = bucketName;
             ListObjectsResponse response = s3Client.ListObjects(listObjectRe
quest);
                List<S30bject> objects = response.S30bjects;
                Console.WriteLine("Object count = {0}", objects.Count);
                Console.WriteLine("Press any key to continue...");
                Console.ReadKey();
            catch (AmazonS3Exception s3Exception)
                Console.WriteLine(s3Exception.Message,
                                  s3Exception.InnerException);
            catch (AmazonSecurityTokenServiceException stsException)
                Console.WriteLine(stsException.Message,
                                 stsException.InnerException);
    private static SessionAWSCredentials GetTemporaryFederatedCredentials(
                                string accessKeyId, string secretAccessKeyId)
          AmazonSecurityTokenServiceConfig config = new AmazonSecurityTokenSer
viceConfig();
            AmazonSecurityTokenServiceClient stsClient =
                new AmazonSecurityTokenServiceClient(
                                             accessKeyId, secretAccessKeyId,
config);
            GetFederationTokenRequest federationTokenRequest =
                                     new GetFederationTokenRequest();
```

```
federationTokenRequest.DurationSeconds = 7200;
            federationTokenRequest.Name = "User1";
            federationTokenRequest.Policy =
  ""Statement"":
 [
      ""Sid"": ""Stmt1311212314284"",
      ""Action"":[""s3:ListBucket""],
      ""Effect"": ""Allow"",
      ""Resource"": "arn:aws:s3:::ExampleBucket""
 ]
";
            GetFederationTokenResponse federationTokenResponse =
                         stsClient.GetFederationToken(federationTokenRequest);
            GetFederationTokenResult federationTokenResult =
                             federationTokenResponse.GetFederationTokenResult;
            Credentials credentials = federationTokenResult.Credentials;
            SessionAWSCredentials sessionCredentials =
                new SessionAWSCredentials(credentials.AccessKeyId,
                                          credentials.SecretAccessKey,
                                          credentials.SessionToken);
            return sessionCredentials;
        }
   }
```

Related Resources

• Using the AWS SDKs and Explorers (p. 325)

Making Requests Using Federated User Temporary Credentials - AWS SDK for PHP

You can provide temporary security credentials to your federated users and applications (see Making Requests (p. 10)) so they can send authenticated requests to access your AWS resources. When requesting these temporary credentials, you must provide a user name and an IAM policy describing the resource permissions you want to grant. By default, the session duration is one hour. You can explicitly set a different duration value when requesting the temporary security credentials for federated users and applications.



Note

To request temporary security credentials for federated users and applications, for added security, you might want to use a dedicated IAM user with only the necessary access permissions. The temporary user you create can never get more permissions than the IAM user who requested the temporary security credentials. For more information, go to AWS Identity and Access Management FAQs.

Making Requests Using Federated User Temporary Credentials

1	Create an instance of the AmazonSTS class by providing your credentials.
2	Create an instance of the CFPolicy by providing the IAM policy that you wish to attach to the temporary security credentials.
3	Execute the AmazonSTS::get_federation_token() method by providing the user name, the policy, and the optional session duration.
	The method returns you temporary security credentials. You can provide these credentials to your federated users.
4	Any federated user who has the temporary security credentials can send requests to Amazon S3 by creating an instance of the AmazonS3 class by providing the temporary security credentials.
	Any methods in the AmazonS3 class that you call use the temporary security credentials to send authenticated requests to Amazon S3.

The following PHP code sample demonstrates the preceding tasks.

```
// In real applications, the following code is part of your trusted code. It
// your security credentials that you used to obtain temporary security creden
tials.
$token = new AmazonSTS();
$policy = new CFPolicy($token, array(
   'Statement' => array(
        array(
            'Sid' => 'randomstatementid' . time(),
            'Action' => array('s3:ListBucket'),
            'Effect' => 'Allow',
            'Resource' => 'arn:aws:s3:::YourBucketName'
        )
   )
));
// Fetch the session credentials.
$response1 = $token->get_federation_token(
                      'User1',
                          'Policy' => $policy->get_json(),
                          'DurationSeconds' => 3600
));
$AccessKeyId = (string)$response1->
               body->GetFederationTokenResult->Credentials->AccessKeyId;
$SecretAccessKey = (string)$response1->
               body->GetFederationTokenResult->Credentials->SecretAccessKey;
$SessionToken = (string)$response1->
                body->GetFederationTokenResult->Credentials->SessionToken;
// The following will be part of your less trusted code. You provide temporary
security
// credentials so it can send authenticated requests to Amazon S3.
```

\$s3 = new AmazonS3(\$AccessKeyId, \$SecretAccessKey, \$SessionToken);
// Send requests to Amazon S3.

Example

The following PHP code example lists keys in the specified bucket. In the code example, you first obtain temporary security credentials for a two hour session for your federated user (User1) and use them to send authenticated requests to Amazon S3.

When requesting temporary credentials for others, for added security, you use the security credentials of an IAM user who has permissions to request temporary security credentials. You can also limit the access permissions of this IAM user to ensure that the IAM user grants only the minimum application specific permissions to the federated user. This sample only lists objects in a specific bucket. Therefore, first create an IAM user with the following policy attached.

The policy allows the IAM user to request temporary security credentials and access permission to only list your AWS resources. For more information about how to create an IAM user, go to Set Up a Group, Grant Permissions, and Add Users in the AWS Identity and Access Management Getting Started Guide.

You can now use the IAM user security credentials to test the following example. The example sends authenticated request to Amazon S3 using temporary security credentials. The example specifies the following policy when requesting temporary security credentials for the federated user (User1) which restricts access to list objects in a specific bucket. You must update the policy and provide your own existing bucket name.

You must update the following sample and provide the bucket name that you specified in the preceding federated user access policy.

```
<?php
require_once '../aws-sdk-for-php/sdk.class.php';
header('Content-Type: text/plain; charset=utf-8');

$bucket = 'ExampleBucket';

$token = new AmazonSTS();

$policy = new CFPolicy($token, array(</pre>
```

```
'Statement' => array(
        array(
            'Sid' => 'randomstatementid' . time(),
            'Action' => array('s3:ListBucket'),
            'Effect' => 'Allow',
            'Resource' => 'arn:aws:s3:::ExampleBucket'
    )
));
// Fetch the session credentials.
$response1 = $token->get_federation_token(
                      'User1',
                       array(
                          'Policy' => $policy->get_json(),
                          'DurationSeconds' => 3600
));
$AccessKeyId = (string)$response1->
                body->GetFederationTokenResult->Credentials->AccessKeyId;
$SecretAccessKey = (string)$response1->
               body->GetFederationTokenResult->Credentials->SecretAccessKey;
$SessionToken = (string)$response1->
                body->GetFederationTokenResult->Credentials->SessionToken;
// Instantiate the class.
$s3 = new AmazonS3($AccessKeyId, $SecretAccessKey, $SessionToken);
// Get object list using temporary credentials.
//$response = $s3->get_object_list($bucket);
$response = $s3->list_objects($bucket);
// Success?
print_r($response);
```

Related Resources

• Using the AWS SDKs and Explorers (p. 325)

Making Requests Using Federated User Temporary Credentials - AWS SDK for Ruby

You can provide temporary security credentials for your federated users and applications (see Making Requests (p. 10)) so that they can send authenticated requests to access your AWS resources. When requesting these temporary credentials from the IAM service, you must provide a user name and an IAM policy describing the resource permissions you want to grant. By default, the session duration is one hour. However, if you are requesting temporary credentials using IAM user credentials, you can explicitly set a different duration value when requesting the temporary security credentials for federated users and applications.



Note

To request temporary security credentials for federated users and applications, for added security, you might want to use a dedicated IAM user with only the necessary access permissions . The temporary user you create can never get more permissions than the IAM user who requested the temporary security credentials. For more information, go to AWS Identity and Access Management FAQs

Making Requests Using Federated User Temporary Security Credentials

1	Create an instance of the AWS Security Token Service client AWS::STS::Session by providing your security credentials.
2	Start a session by calling the new_federated_session method of the STS client you created in the preceding step.
	You will need to provide session information including the user name and an IAM policy that you want to attach to the temporary credentials.
	This method returns your temporary security credentials.

The following Ruby code sample demonstrates the preceding tasks.

Example

The following Ruby code example lists keys in the specified bucket. In the code example, you first obtain temporary security credentials for a two hour session for your federated user (User1) and use them to send authenticated requests to Amazon S3.

When requesting temporary credentials for others, for added security, you use the security credentials of an IAM user who has permissions to request temporary security credentials. You can also limit the access permissions of this IAM user to ensure that the IAM user grants only the minimum application specific permissions when requesting temporary security credentials. This sample only lists objects in a specific bucket. Therefore, first create an IAM user with the following policy attached.

The policy allows the IAM user to request temporary security credentials and access permission to only list your AWS resources. For more information about how to create an IAM user, go to Set Up a Group, Grant Permissions, and Add Users in the AWS Identity and Access Management Getting Started Guide.

You can now use the IAM user security credentials to test the following example. The example sends authenticated request to Amazon S3 using temporary security credentials. The example specifies the following policy when requesting temporary security credentials for the federated user (User1) which restricts access to list objects in a specific bucket (YourBucketName). You must update the policy and provide your own existing bucket name.

```
{
   "Statement":[
      {
        "Sid":"1",
        "Action":["s3:ListBucket"],
        "Effect":"Allow",
        "Resource":"arn:aws:s3:::YourBucketName"
   }
}
```

You must update the following sample and provide the bucket name that you specified in the preceding federated user access policy.

```
require 'rubygems'
require 'aws-sdk'

# In real applications, the following code is part of your trusted code. It has

# your security credentials that you use to obtain temporary security creden
tials.

my_access_key_id = '***Provide Access Key ID***'
```

```
my_secret_key = '***Provide Secret Key***'
bucket name = '*** Provide bucket name ***'
AWS.config({
  :access_key_id => my_access_key_id,
  :secret_access_key => my_secret_key
})
# Start a session with restricted permissions.
sts = AWS::STS.new()
policy = AWS::STS::Policy.new
policy.allow(
  :actions => ["s3:ListBucket"],
  :resources => "arn:aws:s3:::#{bucket_name}")
session = sts.new_federated_session(
  'User1',
  :policy => policy,
  :duration => 2*60*60)
puts "Policy: #{policy.to_json}"
# Get an instance of the S3 interface using the session credentials.
s3 = AWS::S3.new(session.credentials)
# Get a list of all object keys in a bucket.
bucket = s3.buckets[bucket_name].objects.collect(&:key)
puts "No. of Objects = #{bucket.count.to_s}"
puts bucket
```

Making Requests using the REST API

Topics

- Authenticating Requests Using the REST API (p. 47)
- Signing and Authenticating REST Requests (p. 48)
- Virtual Hosting of Buckets (p. 59)
- Request Redirection and the REST API (p. 63)
- Browser-Based Uploads Using POST (p. 65)

This section contains information specific to the Amazon S3 REST API. The examples in this guide use the newer, virtual, hosted-style method for accessing buckets instead of the path-style. For more information, see Working with Amazon S3 Buckets (p. 82)

Following is an example of a virtual hosted-style request to delete the puppy.jpg file from the mybucket bucket.

```
DELETE /puppy.jpg HTTP/1.1
User-Agent: dotnet
Host: mybucket.s3.amazonaws.com
Date: Tue, 15 Jan 2008 21:20:27 +0000
x-amz-date: Tue, 15 Jan 2008 21:20:27 +0000
Authorization: AWS OPN5J17HBGZHT7JJ3X82:k3nL7gH3+PadhTEVn5EXAMPLE
```

Amazon Simple Storage Service Developer Guide Making Requests using the REST API

Following is an example of a path-style version of the same request.

DELETE /mybucket/puppy.jpg HTTP/1.1
User-Agent: dotnet
Host: s3.amazonaws.com
Date: Tue, 15 Jan 2008 21:20:27 +0000
x-amz-date: Tue, 15 Jan 2008 21:20:27 +0000
Authorization: AWS 0PN5J17HBGZHT7JJ3X82:k3nL7gH3+PadhTEVn5EXAMPLE

Amazon S3 supports virtual-hosted-style and path-style access in all Regions. The path-style syntax, however, requires that you use the region-specific endpoint when attempting to access a bucket. For example, if you have a bucket called mybucket that resides in the EU, you want to use path-style syntax, and the object is named puppy. jpg, the correct URI is

http://s3-eu-west-1.amazonaws.com/mybucket/puppy.jpg. You will receive a "PermanentRedirect" error, an HTTP response code 301, and a message indicating what the correct URI is for your resource if you try to access a non US Standard bucket with path-style syntax using:

- http://s3.amazonaws.com
- A different Region endpoint than where the bucket resides, for example, http://s3-euwest-1.amazonaws.com and the bucket was created with the location constraint of Northern-California

Authenticating Requests Using the REST API

When accessing Amazon S3 using REST and SOAP, you must provide the following items in your request so the request can be authenticated:


Request Elements

- AWS Access Key Id—It is the access key id of the identity you are using to send your request.
- **Signature**—Each request must contain a valid request signature, or the request is rejected.


 A request signature is calculated using your Secret Access Key, which is a shared secret known only to you and AWS.
- **Time stamp**—Each request must contain the date and time the request was created, represented as a string in UTC.
- Date—Each request must contain the time stamp of the request.

 Depending on the API you're using, you can provide an expiration date and time for the request instead of or in addition to the time stamp. See the authentication topic for the particular API to determine what the API requires.

Following are the general steps for authenticating requests to Amazon S3. It is assumed you have the necessary security credentials, Access Key ID and Secret Access Key.



1	Construct a request to AWS.
2	Calculate signature using your Secret Access Key.
3	Send the request to Amazon S3. Include your Access Key ID and the signature in your request. Amazon S3 performs the next three steps.



4	Amazon S3 uses the Access Key ID to look up your Secret Access Key.	
5	Amazon S3 calculate a signature from the request data and the Secret Access Key using the same algorithm you used to calculate the signature you sent in the request.	
6	If the signature generated by Amazon S3 matches the one you sent in the request, the request is considered authentic. If the comparison fails, the request is discarded, and Amazon S3 returns an error response.	

Detailed Authentication Information

For detailed information about REST and SOAP authentication, see Signing and Authenticating REST Requests (p. 48) and Authenticating SOAP Requests (p. 352).

Signing and Authenticating REST Requests

Topics

- Using Temporary Security Credentials (p. 49)
- The Authentication Header (p. 49)
- Request Canonicalization for Signing (p. 50)
- Constructing the CanonicalizedResource Element (p. 50)
- Constructing the CanonicalizedAmzHeaders Element (p. 51)
- Positional versus Named HTTP Header StringToSign Elements (p. 52)
- Time Stamp Requirement (p. 52)
- Authentication Examples (p. 52)
- REST Request Signing Problems (p. 57)
- Query String Request Authentication Alternative (p. 57)

Authentication is the process of proving your identity to the system. Identity is an important factor in Amazon S3 access control decisions. Requests are allowed or denied in part based on the identity of the requester. For example, the right to create buckets is reserved for registered developers and (by default) the right to create objects in a bucket is reserved for the owner of the bucket in question. As a developer,

Amazon Simple Storage Service Developer Guide Signing and Authenticating REST Requests

you'll be making requests that invoke these privileges so you'll need to prove your identity to the system by authenticating your requests. This section shows you how.



Note

The content in this section does not apply to HTTP POST. For more information, see Browser-Based Uploads Using POST (p. 65).

The Amazon S3 REST API uses a custom HTTP scheme based on a keyed-HMAC (Hash Message Authentication Code) for authentication. To authenticate a request, you first concatenate selected elements of the request to form a string. You then use your AWS Secret Access Key to calculate the HMAC of that string. Informally, we call this process "signing the request," and we call the output of the HMAC algorithm the "signature" because it simulates the security properties of a real signature. Finally, you add this signature as a parameter of the request, using the syntax described in this section.

When the system receives an authenticated request, it fetches the AWS Secret Access Key that you claim to have, and uses it in the same way to compute a "signature" for the message it received. It then compares the signature it calculated against the signature presented by the requester. If the two signatures match, then the system concludes that the requester must have access to the AWS Secret Access Key, and therefore acts with the authority of the principal to whom the key was issued. If the two signatures do not match, the request is dropped and the system responds with an error message.

Example Authenticated Amazon S3 REST Request

```
GET /photos/puppy.jpg HTTP/1.1
Host: johnsmith.s3.amazonaws.com
Date: Mon, 26 Mar 2007 19:37:58 +0000

Authorization: AWS 0PN5J17HBGZHT7JJ3X82:frJIUN8DYpKDtOLCwo//yllqDzg=
```

Using Temporary Security Credentials

If you are signing your request using temporary security credentials (see Making Requests (p. 10)), you must include the corresponding security token in your request by adding the x-amz-security-token header.

When you obtain temporary security credentials using the AWS Security Token Service API, the response includes temporary security credentials and a session token. You provide the session token value in the x-amz-security-token header when you send requests to Amazon S3. For information about the AWS Security Token Service API provided by IAM, go to Action in the AWS Security Service API Reference Guide.

The Authentication Header

The Amazon S3 REST API uses the standard HTTPAuthorization header to pass authentication information. (The name of the standard header is unfortunate because it carries authentication information, not authorization). Under the Amazon S3 authentication scheme, the Authorization header has the following form.

```
Authorization: AWS AWSAccessKeyId:Signature
```

Developers are issued an AWS Access Key ID and AWS SecretAccess Key when they register. For request authentication, the AWSAccessKeyId element identifies the secret key that was used to compute the signature, and (indirectly) the developer making the request.

The Signature element is the RFC 2104HMAC-SHA1 of selected elements from the request, and so the Signature part of the Authorization header will vary from request to request. If the request signature calculated by the system matches the Signature included with the request, then the requester will have demonstrated possession to the AWSSecret Access Key. The request will then be processed under the identity, and with the authority, of the developer to whom the key was issued.

Following is pseudo-grammar that illustrates the construction of the Authorization request header (\nmeans the Unicode code point U+000A commonly called newline).

```
Authorization = "AWS" + " " + AWSAccessKeyId + ":" + Signature;
Signature = Base64( HMAC-SHA1( UTF-8-Encoding-Of( YourSecretAccessKeyID, StringToSign ) );
StringToSign = HTTP-Verb + "\n" +
Content-MD5 + "\n" +
Content-Type + "\n" +
Date + "\n" +
CanonicalizedAmzHeaders +
CanonicalizedResource;

CanonicalizedResource = [ "/" + Bucket ] +
<HTTP-Request-URI, from the protocol name up to the query string> +
[ sub-resource, if present. For example "?acl", "?location", "?logging", or "?torrent"];
CanonicalizedAmzHeaders = <described below>
```

HMAC-SHA1 is an algorithm defined by RFC 2104 (go to RFC 2104 - Keyed-Hashing for Message Authentication). The algorithm takes as input two byte-strings: a key and a message. For Amazon S3 Request authentication, use your AWS Secret Access Key (YourSecretAccessKeyID) as the key, and the UTF-8 encoding of the StringToSign as the message. The output of HMAC-SHA1 is also a byte string, called the digest. The Signature request parameter is constructed by Base64 encoding this digest.

Request Canonicalization for Signing

Recall that when the system receives an authenticated request, it compares the computed request signature with the signature provided in the request in <code>StringToSign</code>. For that reason, you must compute the signature using the same method used by Amazon S3. We call the process of putting a request in an agreed-upon form for signing "canonicalization".

Constructing the CanonicalizedResource Element

CanonicalizedResource represents the Amazon S3 resource targeted by the request. Construct it for a REST request as follows:

Launch Process

- 1 Start with the empty string (" ").
- If the request specifies a bucket using the HTTP Host header (virtual hosted-style), append the bucket name preceded by a "/" (e.g., "/bucketname"). For path-style requests and requests that don't address a bucket, do nothing. For more information on virtual hosted-style requests, see Virtual Hosting of Buckets (p. 59).

Amazon Simple Storage Service Developer Guide Signing and Authenticating REST Requests

- 3 Append the path part of the un-decoded HTTP Request-URI, up-to but not including the query string.
- If the request addresses a sub-resource, like ?versioning, ?location, ?acl, or ?torrent, or ?versionid append the sub-resource, its value if it has one, and the question mark. Note that in case of multiple sub-resources, sub-resources must be lexicographically sorted by sub-resource name and separated by '&'. e.g. ?acl&versionId=value.

The list of sub-resources that must be included when constructing the CanonicalizedResource Element are: acl, location, logging, notification, partNumber, policy, requestPayment, torrent, uploadld, uploads, versionId, versioning, versions and website.

If the request specifies query string parameters overriding the response header values (see Get Object), append the query string parameters, and its values. When signing you do not encode these values. However, when making the request, you must encode these parameter values. The query string parameters in a GET request include response-content-type,

response-content-language, response-expires, response-cache-control, response-content-disposition, and response-content-encoding.

Elements of the CanonicalizedResource that come from the HTTP Request-URI should be signed literally as they appear in the HTTP request, including URL-Encoding meta characters.

The CanonicalizedResource might be different than the HTTP Request-URI. In particular, if your request uses the HTTP Host header to specify a bucket, the bucket does appear in the HTTP Request-URI. However, the CanonicalizedResource continues to include the bucket. Query string parameters might also appear in the Request-URI but are not included in CanonicalizedResource. For more information, see Virtual Hosting of Buckets (p. 59).

Constructing the CanonicalizedAmzHeaders Element

To construct the CanonicalizedAmzHeaders part of StringToSign, select all HTTP request headers that start with 'x-amz-' (using a case-insensitive comparison) and use the following process.

CanonicalizedAmzHeaders Process

1	Convert each HTTP header name to lower-case. For example, 'X-Amz-Date' becomes 'x-amz-date'.
2	Sort the collection of headers lexicographically by header name.
3	Combine header fields with the same name into one "header-name:comma-separated-value-list" pair as prescribed by RFC 2616, section 4.2, without any white-space between values. For example, the two metadata headers 'x-amz-meta-username: fred' and 'x-amz-meta-username: barney' would be combined into the single header 'x-amz-meta-username: fred, barney'.
4	"Unfold" long headers that span multiple lines (as allowed by RFC 2616, section 4.2) by replacing the folding white-space (including new-line) by a single space.
5	Trim any white-space around the colon in the header. For example, the header 'x-amz-meta-username: fred, barney' would become 'x-amz-meta-username: fred, barney'
6	Finally, append a new-line (U+000A) to each canonicalized header in the resulting list. Construct the CanonicalizedResource element by concatenating all headers in this list into a single string.

Positional versus Named HTTP Header StringToSign Elements

The first few header elements of <code>StringToSign</code> (Content-Type, Date, and Content-MD5) are positional in nature. <code>StringToSign</code> does not include the names of these headers, only their values from the request. In contrast, the <code>'x-amz-'</code> elements are named; Both the header names and the header values appear in <code>StringToSign</code>.

If a positional header called for in the definition of <code>StringToSign</code> is not present in your request, (<code>Content-Type</code> or <code>Content-MD5</code>, for example, are optional for PUT requests, and meaningless for GET requests), substitute the empty string ("") in for that position.

Time Stamp Requirement

A valid time stamp (using either the HTTP Date header or an x-amz-date alternative) is mandatory for authenticated requests. Furthermore, the client time-stamp included with an authenticated request must be within 15 minutes of the Amazon S3 system time when the request is received. If not, the request will fail with the <code>RequestTimeTooSkewed</code> error status code. The intention of these restrictions is to limit the possibility that intercepted requests could be replayed by an adversary. For stronger protection against eavesdropping, use the HTTPS transport for authenticated requests.

Some HTTP client libraries do not expose the ability to set the Date header for a request. If you have trouble including the value of the 'Date' header in the canonicalized headers, you can set the time-stamp for the request using an 'x-amz-date' header instead. The value of the x-amz-date header must be in one of the RFC 2616 formats (http://www.ietf.org/rfc/rfc2616.txt). When an x-amz-date header is present in a request, the system will ignore any Date header when computing the request signature. Therefore, if you include the x-amz-date header, use the empty string for the Date when constructing the StringToSign. See the next section for an example.

Authentication Examples

The examples in this section use the (non-working) credentials in the following table.

Parameter	Value
AWSAccessKeyId	0PN5J17HBGZHT7JJ3X82
AWSSecretAccessKey uV3F3YluFJax1cknvbcGwgjvx4QpvB+leU8dUj2o	

In the example StringToSigns, formatting is not significant and n means the Unicode code point U+000A commonly called newline.

Example Object GET

This example gets an object from the johnsmith bucket.

Request	StringToSign
GET /photos/puppy.jpg HTTP/1.1 Host: johnsmith.s3.amazonaws.com Date: Tue, 27 Mar 2007 19:36:42 +0000	GET\n \n \n
Authorization: AWS 0PN5J17HBG ZHT7JJ3X82: xXjDGYUmKxnwqr5KXNPGldn5LbA=	Tue, 27 Mar 2007 19:36:42 +0000\n/johnsmith/photos/puppy.jpg

Note that the CanonicalizedResource includes the bucket name, but the HTTP Request-URI does not (it is specified by the Host header)

Example Object PUT

This example puts an object into the johnsmith bucket.

Request	StringToSign
PUT /photos/puppy.jpg HTTP/1.1 Content-Type: image/jpeg	PUT\n
Content-Type: Image/jpeg Content-Length: 94328 Host: johnsmith.s3.amazonaws.com	\n image/jpeg\n
Date: Tue, 27 Mar 2007 21:15:45 +0000	Tue, 27 Mar 2007 21:15:45 +0000\n/johnsmith/photos/puppy.jpg
Authorization: AWS OPN5J17HBG ZHT7JJ3X82:	
hcicpDDvL9SsO6AkvxqmIWkmOuQ=	

Note the Content-Type header in the request and in the StringToSign. Also note that the Content-MD5 is left blank in the StringToSign since it is not present in the request.

Example List

This example lists the content of the johnsmith bucket.

Request	StringToSign
GET /?prefix=photos&max-keys=50▮=puppy HTTP/1.1 User-Agent: Mozilla/5.0 Host: johnsmith.s3.amazonaws.com Date: Tue, 27 Mar 2007 19:42:41 +0000	GET\n \n \n Tue, 27 Mar 2007 19:42:41 +0000\n
Authorization: AWS 0PN5J17HBGZHT7JJ3X82:js Rt/rhG+Vtp88HrYL706QhE4w4=	/johnsmith/

Note the trailing slash on the CanonicalizedResource, and the absence of query string parameters.

Example Fetch

This example fetches the access control policy sub-resource for the 'johnsmith' bucket.

Request	StringToSign
GET /?acl HTTP/1.1 Host: johnsmith.s3.amazonaws.com Date: Tue, 27 Mar 2007 19:44:46 +0000	GET\n \n \n
Authorization: AWS 0PN5J17HBG ZHT7JJ3X82:thdUi9VAkzhkniLj96JIrOPGi0g=	Tue, 27 Mar 2007 19:44:46 +0000\n /johnsmith/?acl

Notice how the sub-resource query string parameter is included in the CanonicalizedResource.

Example Delete

This example deletes an object from the 'johnsmith' bucket using the path-style and Date alternative.

Request	StringToSign
DELETE /johnsmith/photos/puppy.jpg HT TP/1.1 User-Agent: dotnet Host: s3.amazonaws.com Date: Tue, 27 Mar 2007 21:20:27 +0000 x-amz-date: Tue, 27 Mar 2007 21:20:26 +0000 Authorization: AWS 0PN5J17HBG ZHT7JJ3X82:k3nL7gH3+PadhTEVn5Ip83xlYzk=	DELETE\n \n \n \n x-amz-date:Tue, 27 Mar 2007 21:20:26 +0000\n /johnsmith/photos/puppy.jpg

Note how we used the alternate 'x-amz-date' method of specifying the date (because our client library prevented us from setting the date, say). In this case the field for the actual 'Date' header is left blank in the StringToSign.

Example Upload

This example uploads an object to a CNAME style virtual hosted bucket with metadata.

Request	StringToSign
PUT /db-backup.dat.gz HTTP/1.1 User-Agent: curl/7.15.5 Host: static.johnsmith.net:8080 Date: Tue, 27 Mar 2007 21:06:08 +0000 x-amz-acl: public-read	PUT\n 4gJE4saaMU4BqNR0kLY+lw==\n application/x-download\n Tue, 27 Mar 2007 21:06:08 +0000\n x-amz-acl:public-read\n
content-type: application/x-download Content-MD5: 4gJE4saaMU4BqNR0kLY+lw== X-Amz-Meta-ReviewedBy: joe@johnsmith.net X-Amz-Meta-ReviewedBy: jane@johnsmith.net X-Amz-Meta-FileChecksum: 0x02661779 X-Amz-Meta-ChecksumAlgorithm: crc32 Content-Disposition: attachment; file name=database.dat Content-Encoding: gzip Content-Length: 5913339 Authorization: AWS OPN5J17HBGZHT7JJ3X82:	x-amz-meta-checksumalgorithm:crc32\nx-amz-meta-filechecksum:0x02661779\nx-amz-meta-reviewedby: joe@johnsmith.net,jane@johns mith.net\n /static.johnsmith.net/db- backup.dat.gz
COF1OtU8Y1b9KDTpZqYkZPX91iI=	

Notice how the 'x-amz-' headers are sorted, white-space trimmed, converted to lowercase, and multiple headers with the same name have been joined using a comma to separate values.

Note how only the Content-Type and Content-MD5 HTTP entity headers appear in the StringToSign. The other Content-* entity headers do not.

Again, note that the <code>CanonicalizedResource</code> includes the bucket name, but the HTTP Request-URI does not (the bucket is specified by the Host header).

Example List All My Buckets

Request	StringToSign
GET / HTTP/1.1 Host: s3.amazonaws.com Date: Wed, 28 Mar 2007 01:29:59 +0000 Authorization: AWS OPN5J17HBG ZHT7JJ3X82:Db+gepJSUbZKwpx1FR0DLtEYoZA=	GET\n \n \n Wed, 28 Mar 2007 01:29:59 +0000\n /

Example Unicode Keys

Request	StringToSign
GET /diction ary/fran%C3%A7ais/pr%c3%a9f%c3%a8re HT TP/1.1 Host: s3.amazonaws.com Date: Wed, 28 Mar 2007 01:49:49 +0000 Authorization: AWS OPN5J17HBGZHT7JJ3X82: dxhSBHoI6eVSPcXJqEghlUzZMnY=	GET\n \n \n Wed, 28 Mar 2007 01:49:49 +0000\n /diction ary/fran%C3%A7ais/pr%c3%a9f%c3%a8re



Note

The elements in StringToSign that were derived from the Request-URI are taken literally, including URL-Encoding and capitalization.

REST Request Signing Problems

When REST request authentication fails, the system responds to the request with an XML error document. The information contained in this error document is meant to help developers diagnose the problem. In particular, the <code>StringToSign</code> element of the <code>SignatureDoesNotMatch</code> error document tells you exactly what request canonicalization the system is using.

Some toolkits silently insert headers that you do not know about beforehand, such as adding the header Content-Type during a PUT. In most of these cases, the value of the inserted header remains constant, allowing you to discover the missing headers using tools such as Ethereal or topmon.

Query String Request Authentication Alternative

You can authenticate certain types of requests by passing the required information as query-string parameters instead of using the Authorization HTTP header. This is useful for enabling direct third-party browser access to your private Amazon S3 data, without proxying the request. The idea is to construct a "pre-signed" request and encode it as a URL that an end-user's browser can retrieve. Additionally, you can limit a pre-signed request by specifying an expiration time.

Creating a Signature

Following is an example query string authenticated Amazon S3 REST request.

```
GET /photos/puppy.jpg
?AWSAccessKeyId=0PN5J17HBGZHT7JJ3X82&Expires=1141889120&Signature=vjbyPxybdZaN
mGa%2ByT272YEAiv4%3D HTTP/1.1
Host: johnsmith.s3.amazonaws.com
Date: Mon, 26 Mar 2007 19:37:58 +0000
```

The query string request authentication method doesn't require any special HTTP headers. Instead, the required authentication elements are specified as query string parameters:

Amazon Simple Storage Service Developer Guide Signing and Authenticating REST Requests

Query String Parameter Name	Example Value	Description
AWSAccessKeyId	0PN5J17HBGZHT7JJ3X82	Your AWS Access Key Id. Specifies the AWS Secret Access Key used to sign the request, and (indirectly) the identity of the developer making the request.
Expires	1141889120	The time when the signature expires, specified as the number of seconds since the epoch (00:00:00 UTC on January 1, 1970). A request received after this time (according to the server), will be rejected.
Signature	vjbyPxybdZaNmGa%2ByT272YEAiv4%3D	The URL encoding of the Base64 encoding of the HMAC-SHA1 of StringToSign.

The query string request authentication method differs slightly from the ordinary method but only in the format of the <code>Signature</code> request parameter and the <code>StringToSign</code> element. Following is pseudo-grammar that illustrates the query string request authentication method.

```
Signature = URL-Encode( Base64( HMAC-SHA1( YourSecretAccessKeyID, UTF-8-Encoding-
Of( StringToSign ) ) ) );

StringToSign = HTTP-VERB + "\n" +
    Content-MD5 + "\n" +
    Content-Type + "\n" +
    Expires + "\n" +
    CanonicalizedAmzHeaders +
    CanonicalizedResource;
```

YourSecretAccessKeyID is the AWS Secret Access Key ID Amazon assigns to you when you sign up to be an Amazon Web Service developer. Notice how the Signature is URL-Encoded to make it suitable for placement in the query-string. Also note that in StringToSign, the HTTP Date positional element has been replaced with Expires. The CanonicalizedAmzHeaders and CanonicalizedResource are the same.

Example Query String Request Authentication

Request	StringToSign
GET /photos/puppy.jpg?AWSAccessKey Id=0PN5J17HBGZHT7JJ3X82& Signature=rucSbH0yNEcP9oM2XN louVI3BH4%3D& Expires=1175139620 HTTP/1.1	GET\n \n \n 1175139620\n
Host: johnsmith.s3.amazonaws.com	/johnsmith/photos/puppy.jpg

We assume that when a browser makes the GET request, it won't provide a Content-MD5 or a Content-Type header, nor will it set any x-amz- headers, so those parts of the <code>StringToSign</code> are left blank.

Using Base64 Encoding

HMAC request signatures must be Base64 encoded. Base64 encoding converts the signature into a simple ASCII string that can be attached to the request. Two characters, plus (+) and forward slash (/), cannot be used directly and must be encoded if used in a URI. For example, if the authentication code includes a plus (+) sign, encode it as %2B; in the request. Encode a forward slash as %2F;.

For examples of Base64 encoding, refer to the Amazon S3 code samples.

Virtual Hosting of Buckets

Topics

- HTTP Host Header Bucket Specification (p. 60)
- Examples (p. 60)
- Customizing Amazon S3 URLs with CNAMEs (p. 62)
- Limitations (p. 63)
- Backward Compatibility (p. 63)

Virtual Hosting, in general, is the practice of serving multiple web sites from a single web server. One way to differentiate sites is by using the apparent host name of the request instead of just the path name part of the URI. An ordinary Amazon S3 REST request specifies a bucket using the first slash delimited component of the Request-URI path. Alternatively, using Amazon S3 Virtual Hosting, you can address a bucket in a REST API call using the HTTP Host header. In practice, Amazon S3 interprets Host as meaning that most buckets are automatically accessible (for limited types of requests) at http://bucketname.s3.amazonaws.com. Furthermore, by naming your bucket after your registered domain name and by making that name a DNS alias for Amazon S3, you can completely customize the URL of your Amazon S3 resources, for example: http://my.bucketname.com/

Besides the attractiveness of customized URLs, a second benefit of virtual hosting is the ability to publish to the 'root directory' of your bucket's virtual server. This can be important because many existing applications search for files in this standard location. For example, favicon.ico, robots.txt, crossdomain.xml, are all expected to be found at the root.



Important

Amazon S3 supports virtual-hosted-style and path-style access in all Regions. The path-style syntax, however, requires that you use the region-specific endpoint when attempting to access

Amazon Simple Storage Service Developer Guide Virtual Hosting of Buckets

a bucket. For example, if you have a bucket called mybucket that resides in the EU, you want to use path-style syntax, and the object is named puppy.jpg, the correct URI is http://s3-eu-west-1.amazonaws.com/mybucket/puppy.jpg. You will receive a "PermanentRedirect" error, an HTTP response code 301, and a message indicating what the correct URI is for your resource if you try to access a non US Standard bucket with path-style syntax using:

- http://s3.amazonaws.com
- A different Region endpoint than where the bucket resides, for example, http://s3-euwest-1.amazonaws.com and the bucket was created with the location constraint of Northern-California

HTTP Host Header Bucket Specification

As long as your GET request does not use the SSL endpoint, you can specify the bucket for the request using the HTTP Host header. The Host header in a REST request is interpreted as follows:

- If the Host header is omitted or its value is 's3.amazonaws.com', the bucket for the request will be the first slash-delimited component of the Request-URI, and the key for the request will be the rest of the Request-URI. This is the ordinary method, as illustrated by the first and second example in the following table. Note that omitting the Host header is only legal for HTTP 1.0 requests.
- Otherwise, if the value of the Host header ends in '.s3.amazonaws.com', then the bucket name is the leading component of the Host header's value up to '.s3.amazonaws.com'. The key for the request is the Request-URI. This interpretation exposes buckets as sub-domains of s3.amazonaws.com, and is illustrated by the third and fourth example in the following table.
- Otherwise, the bucket for the request will be the lower-cased value of the Host header and the key for
 the request is the Request-URI. This interpretation is useful when you have registered the same DNS
 name as your bucket name, and have configured that name to be a CNAME alias for Amazon S3. The
 procedure for registering domain names and configuring DNS is outside the scope of this document,
 but the result is illustrated by the final example in the following table.

Examples

This section provides example URLs and requests.

Amazon Simple Storage Service Developer Guide Virtual Hosting of Buckets

Example Path Style Method

This example uses johnsmith.net as the bucket name and homepage.html as the key name.

Following is the example URL.

```
http://s3.amazonaws.com/johnsmith/homepage.html
```

Following is the example request.

```
GET /johnsmith/homepage.html HTTP/1.1
Host: s3.amazonaws.com
```

Following is the example request with HTTP 1.0 omitting the host header.

```
GET /johnsmith/homepage.html
HTTP/1.0
Host: s3.amazonaws.com
```

For information about DNS compatible names, see Limitations (p. 63). For more information about keys, see Keys (p. 3).

Example Virtual Hosted Style Method

This example uses johnsmith.net as the bucket name and homepage.html as the key name.

Following is the example URL.

```
http://johnsmith.s3.amazonaws.com/homepage.html
```

Following is the example request.

```
GET /homepage.html HTTP/1.1
Host: johnsmith.s3.amazonaws.com
```

Following is the example request with the incorrect case. Notice that sentence case is irrelevant. However, uppercase buckets are not accessible using this method.

```
GET /homepage.html HTTP/1.1
Host: JohnSmith.s3.amazonaws.com
```

Amazon Simple Storage Service Developer Guide Virtual Hosting of Buckets

Example CNAME Method

This example uses www.johnsmith.net as the bucket name and homepage.html as the key name. To use this method, you must configure your DNS name as a CNAME alias for bucketname.s3.amazonaws.com.

Following is the example URL.

```
http://www.johnsmith.net/homepage.html
```

Following is the example request.

```
GET /homepage.html HTTP/1.1
Host: www.johnsmith.net
```

Customizing Amazon S3 URLs with CNAMEs

Depending on your needs, you might not want "s3.amazonaws.com" to appear on your web site or service. For example, if you host your web site's images on Amazon S3, you might prefer http://images.johnsmith.net/asopposed to http://johnsmith-images.s3.amazonaws.com/.

The bucket name must be the same as the CNAME. So http://images.johnsmith.net/filename would be the same as http://images.johnsmith.net.s3.amazonaws.com/filename if a CNAME were created to map images.johnsmith.net to images.johnsmith.net.s3.amazonaws.com.

Any bucket with a DNS compatible name may be referenced as follows:

```
http://[BucketName].s3.amazonaws.com/[Filename], for example, http://images.johnsmith.net.s3.amazonaws.com/mydog.jpg. Using CNAME you can map images.johnsmith.net to an Amazon S3 host name so the previous URL could become: http://images.johnsmith.net/mydog.jpg.
```

The CNAME DNS record should alias your domain name to the appropriate virtual hosted style host name. For example, if your bucket name (and domain name) is images.johnsmith.net, the CNAME record should alias to images.johnsmith.net.s3.amazonaws.com.

```
images.johnsmith.net CNAME images.johnsmith.net.s3.amazonaws.com.
```

Setting the alias target to s3.amazonaws.com also works but may result in extra HTTP redirects.



Note

Amazon S3 only sees the original host name and is unaware of the CNAME mapping used to resolve the request.

Any Amazon S3 endpoint can be used in a CNAME, for example, he s3-ap-southeast-1.amazonaws.com can be used in CNAMEs. For more information about endpoints, see Request Endpoints (p. 12).

To associate a host name with an Amazon S3 bucket using CNAMEs

- 1. Select a host name that belongs to a domain you control.

 This example uses the images subdomain of the johnsmith.net domain.
- 2. Create a bucket that matches the host name.

 In this example, the host and bucket names are images.johnsmith.net.



Note

Your bucket name must exactly match the host name.

3. Create a CNAME record that defines the host name as an alias for the Amazon S3 bucket. For example:

images.johnsmith.net CNAME images.johnsmith.net.s3.amazonaws.com



Important

For request routing reasons, the CNAME record must be defined exactly as shown in the preceding example. Otherwise, it might appear to operate correctly, but will eventually result in unpredictable behavior.



Note

The exact procedure for configuring DNS depends on your DNS server or DNS provider and is beyond scope of this document.

Limitations

Because DNS names are case insensitive, only lower-case buckets are addressable using the virtual hosting method. For more information, see Bucket Restrictions and Limitations (p. 83).

Specifying the bucket for the request using the HTTP Host header is supported for non-SSL requests and when using the REST API. You cannot specify the bucket in SOAP by using a different endpoint.

Backward Compatibility

Early versions of Amazon S3 incorrectly ignored the HTTP Host header. Applications that depend on this undocumented behavior must be updated to set the Host header correctly. Because Amazon S3 determines the bucket name from Host when present, the most likely symptom of this problem is to receive an unexpected NoSuchBucket error result code.

Request Redirection and the REST API

Topics

- Redirects and HTTP User-Agents (p. 63)
- Redirects and 100-Continue (p. 64)
- Redirect Example (p. 64)

This section describes how to handle HTTP redirects using REST. For general information about Amazon S3 redirects, see Request Redirection and the REST API (p. 296).

Redirects and HTTP User-Agents

Programs that use the Amazon S3 REST API should handle redirects either at the application layer or the HTTP layer. Many HTTP client libraries and user agents can be configured to correctly handle redirects automatically. However, many others have incorrect or incomplete redirect implementations.

Before relying on a library to fulfill the redirect requirement, test the following cases:

Launch Process

1	Verify all HTTP request headers are correctly included in the redirected request (the second request after receiving a redirect) including HTTP standards such as Authorization and Date.
2	Verify non-GET redirects, such as PUT and DELETE, work correctly.
3	Verify large PUT requests follow redirects correctly.
4	Verify PUT requests follow redirects correctly if the 100-continue response takes a long time to arrive.

HTTP user-agents that strictly conform to RFC2616 might require explicit confirmation before following a redirect when the HTTP request method is not GET or HEAD. It is generally safe to follow redirects generated by Amazon S3 automatically, as the system will only issue redirects to hosts within the amazonaws.com domain and the effect of the redirected request will be the same as the original request.

Redirects and 100-Continue

To simplify redirect handling, improve efficiencies, and avoid the costs associated with sending a redirected request body twice, configure your application to use 100-continues for PUT operations. When your application uses 100-continue, it does not send the request body until it receives an acknowledgement. If the message is rejected based on the headers, the body of the message is not sent. For more information about 100-continue, go to RFC 2616 Section 8.2.3



Note

According to RFC 2616, when using Expect: Continue with an unknown HTTP server, you should not wait an indefinite period before sending the request body. This is because some HTTP servers do not recognize 100-continue. However, Amazon S3 does recognize if your request contains an Expect: Continue and will respond with a provisional 100-continue status or a final status code. Additionally, no redirect error will occur after receiving the provisional 100 continue go-ahead. This will help you avoid receiving a redirect response while you are still writing the request body.

Redirect Example

This section provides an example of client-server interaction using HTTP redirects and 100-continue.

Following is a sample PUT to the quotes.s3.amazonaws.com bucket.

```
PUT /nelson.txt HTTP/1.1
Host: quotes.s3.amazonaws.com
Date: Mon, 15 Oct 2007 22:18:46 +0000

Content-Length: 6
Expect: 100-continue
```

Amazon S3 returns the following:

```
HTTP/1.1 307 Temporary Redirect
Location: http://quotes.s3-4c25d83b.amazonaws.com/nelson.txt?rk=8d47490b
Content-Type: application/xml
```

Amazon Simple Storage Service Developer Guide Browser-Based Uploads Using POST

The client follows the redirect response and issues a new request to the quotes.s3-4c25d83b.amazonaws.com temporary endpoint.

```
PUT /nelson.txt?rk=8d47490b HTTP/1.1
Host: quotes.s3-4c25d83b.amazonaws.com
Date: Mon, 15 Oct 2007 22:18:46 +0000

Content-Length: 6
Expect: 100-continue
```

Amazon S3 returns a 100-continue indicating the client should proceed with sending the request body.

```
HTTP/1.1 100 Continue
```

The client sends the request body.

```
ha ha\n
```

Amazon S3 returns the final response.

```
HTTP/1.1 200 OK
Date: Mon, 15 Oct 2007 22:18:48 GMT

ETag: "a2c8d6b872054293afd41061e93bc289"
Content-Length: 0
Server: AmazonS3
```


Browser-Based Uploads Using POST

Topics

- HTML Forms (p. 66)
- Upload Examples (p. 74)
- POST with Adobe Flash (p. 80)

Amazon S3 supports POST, which allows your users to upload content directly to Amazon S3. POST is designed to simplify uploads, reduce upload latency, and save you money on applications where users upload data to store in Amazon S3.

The following figure shows an upload using Amazon S3 POST.



Uploading Using POST

1	The user opens a web browser and accesses your web page.
2	Your web page contains an HTTP form that contains all the information necessary for the user to upload content to Amazon S3.
3	The user uploads content directly to Amazon S3.



Note

Query string authentication is not supported for POST.

HTML Forms

Topics

- HTML Form Encoding (p. 67)
- HTML Form Declaration (p. 67)
- HTML Form Fields (p. 68)
- Policy Construction (p. 70)
- Constructing a Signature (p. 73)
- Redirection (p. 73)

When communicating with Amazon S3, you normally use the REST or SOAP APIs to perform put, get, delete, and other operations. With POST, users upload data directly to Amazon S3 through their browsers, which do not understand SOAP APIs or how to make a REST PUT request.

To allow users to upload content to Amazon S3 using their browsers, you use HTML forms. HTML Forms consist of a form declaration and form fields. The form declaration contains high level information about the request. The form fields contain detailed information about the request as well as the policy that is used to authenticate it and make sure that it meets conditions that you specify.



Note

The form data and boundaries (excluding the contents of the file) cannot exceed 20K.

This section describes how to use HTML forms.

HTML Form Encoding

The form and policy must be UTF-8 encoded. You can apply UTF-8 encoding to the form by specifying it in the HTML heading or as a request header.



Note

The HTML form declaration does not accept query string authentication parameters. For information about query string authentication, see Using Query String Authentication (p. 245).

Following is an example of UTF-8 encoding in the HTML heading.

```
<html>
  <head>
    ...
    <meta http-equiv="Content-Type" content="text/html; charset=UTF-8" />
    ...
  </head>
  <body>
```

Following is an example of UTF-8 encoding in a request header.

```
Content-Type: text/html; charset=UTF-8
```

HTML Form Declaration

The form declaration has three components: the action, the method, and the enclosure type. If any of these values is improperly set, the request fails.

The action specifies the URL that processes the request, which must be set to the URL of the bucket. For example, if the name of your bucket is "johnsmith", the URL is "http://johnsmith.s3.amazonaws.com/".



Note

The key name is specified in a form field.

The method must be POST.

The enclosure type (enctype) must be specified and must be set to multipart/form-data (go to RFC 1867) for both file uploads and text area uploads.

Example

This is a form declaration for the bucket "johnsmith".

```
<form action="http://johnsmith.s3.amazonaws.com/" method="post"
enctype="multipart/form-data">
```

HTML Form Fields

Following is a table that describes a list of fields that can be used within a form.



Note

The variable \${filename} is automatically replaced with the name of the file provided by the user and is recognized by all form fields. If the browser or client provides a full or partial path to the file, only the text following the last slash (/) or backslash (\) will be used (e.g., "C:\Program Files\directory1\file.txt" will be interpreted as "file.txt"). If no file or filename is provided, the variable is replaced with an empty string.

Element Name	Description	Required
AWSAccessKeyId	The AWS Access Key ID of the owner of the bucket who grants an Anonymous user access for a request that satisfies the set of constraints in the Policy. This is required if a policy document is included with the request.	Conditional
acl	Specifies an Amazon S3 access control list. If an invalid access control list is specified, an error is generated. For more information on ACLs, see Amazon S3 ACLs (p. 7). Type: String Default: private Valid Values: private public-read public-read-write authenticated-read bucket-owner-full-control	No
Cache-Control, Content-Type, Content-Disposition, Content-Encoding, Expires	REST-specific headers. For more information, see PUT Object.	No
key	The name of the uploaded key. To use the filename provided by the user, use the \${filename} variable. For example, if the user Betty uploads the file the file lolcatz.jpg and you specify /user/betty/\${filename}, the file is stored as /user/betty/lolcatz.jpg. For more information, see Using Keys.	Yes
policy	Security Policy describing what is permitted in the request. Requests without a security policy are considered anonymous and only work on publicly writable buckets.	No

Element Name	Description	Required
success_action_redirect, redirect	The URL to which the client is redirected upon successful upload. Amazon S3 appends the bucket, key and etag values as query string parameters to the URL. If success_action_redirect is not specified, Amazon S3 returns the empty document type specified in the success_action_status field. If Amazon S3 cannot interpret the URL, it acts as if the field is not present. If the upload fails, Amazon S3 displays an error and does not redirect the user to a URL. For more information, see Redirection (p. 73). Note The redirect field name is deprecated and support for the redirect field name will be removed in the future.	No
success_action_status	The status code returned to the client upon successful upload if success_action_redirect is not specified. Accepts the values 200, 201, or 204 (default). If the value is set to 200 or 204, Amazon S3 returns an empty document with a 200 or 204 status code. If the value is set to 201, Amazon S3 returns an XML document with a 201 status code. For information on the content of the XML document, see POST Object. If the value is not set or if it is set to an invalid value, Amazon S3 returns an empty document with a 204 status code. Note Some versions of the Adobe Flash player do not properly handle HTTP responses with an empty body. To support uploads through Adobe Flash, we recommend setting success_action_status to 201.	No
signature	The HMAC signature constructed using the secret key of the provided AWSAccessKeyld. This is required if a policy document is included with the request. For more information, see Using Auth Access.	Conditional

Element Name	Description	Required
x-amz-security-token	Amazon DevPay security token. Each request that uses Amazon DevPay requires two x-amz-security-token form fields: one for the product token and one for the user token. For more information, see Using DevPay.	No
Other field names prefixed with x-amz-meta-	User-specified metadata. Amazon S3 does not validate or use this data. For more information, see PUT Object.	No
file	File or text content. The file or content must be the last field in the form, as any fields below it are ignored. You cannot upload more than one file at a time.	Yes

Policy Construction

Topics

- Expiration (p. 71)
- Conditions (p. 71)
- Condition Matching (p. 72)
- Character Escaping (p. 73)

The policy is a UTF-8 and Base64 encoded JSON document that specifies conditions which the request must meet and is used to authenticate the content. Depending on how you design your policy documents, you can use them per-upload, per-user, for all uploads, or according to other designs that meet your needs.



Note

Although the policy document is optional, we highly recommend it over making a bucket publicly writable.

Following is an example of a policy document.

```
{ "expiration": "2007-12-01T12:00:00.000Z",

   "conditions": [
          {"acl": "public-read" },
          {"bucket": "johnsmith" },

          ["starts-with", "$key", "user/eric/"],
]
}
```

The policy document contains the expiration and conditions.

Expiration

The expiration specifies the expiration date of the policy in ISO8601 GMT date format. For example, "2007-12-01T12:00:00.000Z" specifies that the policy is not valid after 12:00 GMT on 2007-12-01. Expiration is required in a policy.

Conditions

The conditions in the policy document are used to validate the contents of the uploaded object. Each form field that you specify in the form (except AWSAccessKeyld, signature, file, policy, and field names that have an x-ignore- prefix) must be included in the list of conditions.



Note

If you have multiple fields with the same name, the values must be separated by commas. For example, if you have two fields named "x-amz-meta-tag" and the first one has a value of "Ninja" and second has a value of "Stallman", you would set the policy document to Ninja, Stallman. All variables within the form are expanded prior to validating the policy. Therefore, all condition matching should be against the expanded fields. For example, if you set the key field to user/betty/\${filename}, your policy might be ["starts-with", "\$key", "user/betty/\${filename}"]. Do not enter ["starts-with", "\$key", "user/betty/\${filename}"]. For more information, see Condition Matching (p. 72).

Policy document conditions are described in the following table.

Element Name	Description
acl	Specifies conditions the ACL must meet. Supports exact matching and starts-with.
content-length-range	Specifies the minimum and maximum allowable size for the uploaded content. Supports range matching.
Cache-Control, Content-Type, Content-Disposition, Content-Encoding, Expires	REST-specific headers. Supports exact matching and starts-with.
key	The name of the uploaded key. Supports exact matching and starts-with.
success_action_redirect, redirect	The URL to which the client is redirected upon successful upload. Supports exact matching and starts-with.
success_action_status	The status code returned to the client upon successful upload if success_action_redirect is not specified. Supports exact matching.

Element Name	Description
x-amz-security-token	Amazon DevPay security token. Each request that uses Amazon DevPay requires two x-amz-security-token form fields: one for the product token and one for the user token. As a result, the values must be separated by commas. For example, if the user token is $eW91dHViZQ== \text{ and the product token is }b0hnNVNKWVJIQTA=, you set the policy entry to: { "x-amz-security-token": "eW91dHViZQ==,b0hnNVNKWVJIQTA=" }. For more information about Amazon DevPay, see Using DevPay .$
Other field names prefixed with x-amz-meta-	User-specified metadata. Supports exact matching and starts-with.



Note

If your toolkit adds additional fields (e.g., Flash adds filename), you must add them to the policy document. If you can control this functionality, prefix x-ignore- to the field so Amazon S3 ignores the feature and it won't affect future versions of this feature.

Condition Matching

Following is a table that describes condition matching types. Although you must specify one condition for each form field that you specify in the form, you can create more complex matching criteria by specifying multiple conditions for a form field.

Condition	Description
Exact Matches	Exact matches verify that fields match specific values. This example indicates that the ACL must be set to public-read:
	{"acl": "public-read" }
	This example is an alternate way to indicate that the ACL must be set to public-read:
	["eq", "\$acl", "public-read"]
Starts With	If the value must start with a certain value, use starts-with. This example indicates that the key must start with user/betty:
	["starts-with", "\$key", "user/betty/"]
Matching Any Content	To configure the policy to allow any content within a field, use starts-with with an empty value. This example allows any success_action_redirect:
	["starts-with", "\$success_action_redirect", ""]

Condition	Description
Specifying Ranges	For fields that accept ranges, separate the upper and lower ranges with a comma. This example allows a file size from 1 to 10 megabytes:
	["content-length-range", 1048579, 10485760]

Character Escaping

Characters that must be escaped within a policy document are described in the following table.

Escape Sequence	Description
//	Backslash
\\$	Dollar symbol
\b	Backspace
\f	Form feed
\n	New line
\r	Carriage return
\t	Horizontal tab
\v	Vertical tab
\uxxxx	All Unicode characters

Constructing a Signature

\$	Description
1	Encode the policy using UTF-8.
2	Encode those UTF-8 bytes using Base64.
3	Sign the policy with your Secret Access Key using HMAC SHA-1.
4	Encode the SHA-1 signature using Base64.

For general information about authentication, see Using Auth Access .

Redirection

This section describes how to handle redirects.

General Redirection

On completion of the POST, the user is redirected to the location that you specified in the success_action_redirect field. If Amazon S3 cannot interpret the URL, it ignores the success_action_redirect field.

If success_action_redirect is not specified, Amazon S3 returns the empty document type specified in the success_action_status field.

If the POST fails, Amazon S3 displays an error and does not provide a redirect.

Pre-Upload Redirection

If your bucket was created using <CreateBucketConfiguration>, your end-users might require a redirect. If this occurs, some browsers might handle the redirect incorrectly. This is relatively rare, but is most likely to occur right after a bucket is created.

Upload Examples

Topics

- File Upload (p. 74)
- Text Area Upload (p. 77)

File Upload

This example shows the complete process for constructing a policy and form to upload a file attachment.

Policy and Form Construction

Following is a policy that supports uploads to Amazon S3 for the johnsmith bucket.

```
{ "expiration": "2007-12-01T12:00:00.000Z",
    "conditions": [
          {"bucket": "johnsmith"},
          ["starts-with", "$key", "user/eric/"],
          {"acl": "public-read"},
          {"success_action_redirect": "http://johnsmith.s3.amazonaws.com/successful_up
load.html"},
          ["starts-with", "$Content-Type", "image/"],
          {"x-amz-meta-uuid": "14365123651274"},
          ["starts-with", "$x-amz-meta-tag", ""]
          ]
}
```

This policy requires the following:

- The upload must occur before 12:00 GMT on 2007-12-01
- The content must be uploaded to the johnsmith bucket
- The key must start with "user/eric/"
- The ACL is set to public-read
- The success_action_redirect is set to http://johnsmith.s3.amazonaws.com/successful_upload.html
- · The object is an image file
- The x-amz-meta-uuid tag must be set to 14365123651274

The x-amz-meta-tag can contain any value

Following is a Base64 encoded version of this policy.

eyAiZXhwaXJhdGlvbiI6ICIyMDA3LTEyLTAxVDEyOjAwOjAwLjAwMFoiLAogICJjb25kaXRpb25zI jogWwogICAgeyJidWNrZXQiOiAiam9obnNtaXRoIn0sCiAgICBbInN0YXJ0cyl3aXRoIiwgIiRrZXkiL CAidXNlci9lcmljLyJdLAogICAgeyJhY2wiOiAicHVibGljLXJlYWQifSwKICAgIH sic3VjY2Vzc19hY3Rpb25fcmVkaXJlY3QiOiAiaHR0cDovL2pvaG5zbWl0aC5zMy5hb WF6b25hd3MuY29tL3N1Y2Nlc3NmdWxfdXBsb2FkLmh0bWwifSwKICAgIFsic3RhcnRzLXdpdGgiL CAiJENvbnRlbnQtVHlwZSIsICJpbWFnZS8iXSwKICAgIHsieClhbXotbWV0YS1ldWlkIjogIjE0MzYlMT IzNjUxMjc0In0sCiAgICBbInN0YXJ0cyl3aXRoIiwgIiR4LWFteiltZXRhLXRhZyIsICIiXQo gIF0KfQo=

The secret key ID is uV3F3YluFJax1cknvbcGwgjvx4QpvB+leU8dUj2o, so ORavWzkygo6QX9caELEqKi9kDbU= is the signature for the preceding Policy document.

Following is a form that supports a POST to the johnsmith.net bucket using this policy.

```
<html>
  <head>
   <meta http-equiv="Content-Type" content="text/html; charset=UTF-8" />
  </head>
  <body>
 <form action="http://johnsmith.s3.amazonaws.com/" method="post" enctype="mul</pre>
tipart/form-data">
   Key to upload: <input type="input" name="key" value="user/eric/" /><br />
    <input type="hidden" name="acl" value="public-read" />
    <input type="hidden" name="success_action_redirect" value="http://johns</pre>
mith.s3.amazonaws.com/successful_upload.html" />
    Content-Type: <input type="input" name="Content-Type" value="image/jpeg"
/><br />
   <input type="hidden" name="x-amz-meta-uuid" value="14365123651274" />
   Tags for File: <input type="input" name="x-amz-meta-tag" value="" /><br />
   <input type="hidden" name="AWSAccessKeyId" value="15B4D3461F177624206A" />
   <input type="hidden" name="Policy" value="POLICY" />
   <input type="hidden" name="Signature" value="SIGNATURE" />
   File: <input type="file" name="file" /> <br />
    <!-- The elements after this will be ignored -->
    <input type="submit" name="submit" value="Upload to Amazon S3" />
  </form>
  . . .
</html>
```

Sample Request

This request assumes that the image uploaded is 117,108 bytes; the image data is not included.

```
POST / HTTP/1.1
Host: johnsmith.s3.amazonaws.com
User-Agent: Mozilla/5.0 (Windows; U; Windows NT 5.1; en-US; rv:1.8.1.10)
Gecko/20071115 Firefox/2.0.0.10
Accept: text/xml,application/xml,applica
tion/xhtml+xml,text/html;q=0.9,text/plain;q=0.8,image/png,*/*;q=0.5
Accept-Language: en-us, en; q=0.5
Accept-Encoding: gzip, deflate
Accept-Charset: ISO-8859-1, utf-8; q=0.7, *; q=0.7
Keep-Alive: 300
Connection: keep-alive
Content-Type: multipart/form-data; boundary=9431149156168
Content-Length: 118698
--9431149156168
Content-Disposition: form-data; name="key"
user/eric/MyPicture.jpg
--9431149156168
Content-Disposition: form-data; name="acl"
public-read
--9431149156168
Content-Disposition: form-data; name="success_action_redirect"
http://johnsmith.s3.amazonaws.com/successful_upload.html
--9431149156168
Content-Disposition: form-data; name="Content-Type"
image/jpeg
--9431149156168
Content-Disposition: form-data; name="x-amz-meta-uuid"
14365123651274
--9431149156168
Content-Disposition: form-data; name="x-amz-meta-tag"
Some, Tag, For, Picture
--9431149156168
Content-Disposition: form-data; name="AWSAccessKeyId"
15B4D3461F177624206A
--9431149156168
Content-Disposition: form-data; name="Policy"
eyAiZXhwaXJhdGlvbiI6ICIyMDA3LTEyLTAxVDEyOjAwOjAwLjAwMFoiLAogICJjb25kaXRpb25zI
jogWwogICAgeyJidWNrZXQiOiAiam9obnNtaXRoIn0sCiAgICBbInN0YXJ0cy13aXRoIiwgIiRrZXkiL
CAidXNlci9lcmljLyJdLAogICAgeyJhY2wiOiAicHVibGljLXJlYWQifSwKICAgIH
sic3VjY2Vzc19hY3Rpb25fcmVkaXJ1Y3Qi0iAiaHR0cDovL2pvaG5zbW10aC5zMy5hb
WF6b25hd3MuY29tL3N1Y2N1c3NmdWxfdXBsb2FkLmh0bWwifSwKICAgIFsic3RhcnRzLXdpdGgiL
CAiJENvbnRlbnQtVHlwZSIsICJpbWFnZS8iXSwKICAgIHsieC1hbXotbWV0YS11dWlkIjogIjE0MzY1MT
IzNjUxMjc0In0sCiAgICBbInN0YXJ0cy13aXRoIiwgIiR4LWFtei1tZXRhLXRhZyIsICIiXQo
gIF0KfQo=
--9431149156168
Content-Disposition: form-data; name="Signature"
ORavWzkygo6QX9caELEqKi9kDbU=
--9431149156168
```

```
Content-Disposition: form-data; name="file"; filename="MyFilename.jpg"
Content-Type: image/jpeg

...file content...
--9431149156168
Content-Disposition: form-data; name="submit"

Upload to Amazon S3
--9431149156168--
```

Sample Response

```
HTTP/1.1 303 Redirect
x-amz-request-id: 1AEE782442F35865
x-amz-id-2: cxzFLJRatFHy+NGtaDFRR8YvI9BHmgLxjvJzNiGGICARZ/mVXHj7T+qQKhdpzHFh
Content-Type: application/xml
Date: Wed, 14 Nov 2007 21:21:33 GMT
Connection: close
Location: http://johnsmith.s3.amazonaws.com/successful_upload.html?bucket=john
smith&key=user/eric/MyPicture.jpg&etag="39d459df
bc0faabbb5e179358dfb94c3"
Server: AmazonS3
```

Text Area Upload

Topics

- Policy and Form Construction (p. 77)
- Sample Request (p. 79)
- Sample Response (p. 80)

This example shows the complete process for constructing a policy and form to upload a text area. This is useful for submitting user-created content such as blog postings.

Policy and Form Construction

Following is a policy that supports text area uploads to Amazon S3 for the johnsmith bucket.

This policy requires the following:

- The upload must occur before 12:00 GMT on 2007-12-01
- The content must be uploaded to the johnsmith bucket

- The key must start with "user/eric/"
- The ACL is set to public-read
- The success_action_redirect is set to http://johnsmith.s3.amazonaws.com/new_post.html
- · The object is HTML text
- The x-amz-meta-uuid tag must be set to 14365123651274
- The x-amz-meta-tag can contain any value

Following is a Base64 encoded version of this policy.

```
eyAiZXhwaXJhdGlvbiI6ICIyMDA3LTEyLTAxVDEyOjAwOjAwLjAwMFoiLAogICJjb25kaXR
pb25zIjogWwogICAgeyJidWNrZXQiOiAiam9obnNtaXRoIn0sCiAgICBbInN0YXJ0cy13aXRoIiw
gIiRrZXkiLCAidXNlci9lcmljLyJd
LAogICAgeyJhY2wiOiAicHVibGljLXJlYWQifSwKICAgIHsic3VjY2Vzc19hY3Rpb25fcm
VkaXJlY3QiOiAiaHR0cDovL2pvaG5zbWl0a
C5zMy5hbWF6b25hd3MuY29tL25ld19wb3N0Lmh0bWwifSwKICAgIFsiZXEiLCAiJENvbnRlbnQtVHl
wZSIsICJ0ZXh0L2h0bWwiXSwKI
CAgIHsieClhbXotbWV0YS1ldWlkIjogIjE0MzY1MTIzNjUxMjc0In0sCiAgICBbInN0YXJ0cy13aXRoIi
wgIiR4LWFteiltZXRhLXRhZy
IsICIiXQogIF0KfQo=
```

The secret key ID is uV3F3YluFJax1cknvbcGwgjvx4QpvB+leU8dUj2o, so qA7FWXKq6VvU68119KdveT1cWgE= is the signature for the preceding Policy document.

Following is a form that supports a POST to the johnsmith.net bucket using this policy.

```
<html>
  <head>
    <meta http-equiv="Content-Type" content="text/html; charset=UTF-8" />
  </head>
  <body>
  . . .
 <form action="http://johnsmith.s3.amazonaws.com/" method="post" enctype="mul</pre>
tipart/form-data">
   Key to upload: <input type="input" name="key" value="user/eric/" /><br />
    <input type="hidden" name="acl" value="public-read" />
    <input type="hidden" name="success_action_redirect" value="http://johns</pre>
mith.s3.amazonaws.com/new_post.html" />
    <input type="hidden" name="Content-Type" value="text/html" />
   <input type="hidden" name="x-amz-meta-uuid" value="14365123651274" />
   Tags for File: <input type="input" name="x-amz-meta-tag" value="" /><br />
    <input type="hidden" name="AWSAccessKeyId" value="15B4D3461F177624206A" />
   <input type="hidden" name="Policy" value="POLICY" />
    <input type="hidden" name="Signature" value="SIGNATURE" />
   Entry: <textarea name="file" cols="60" rows="10">
Your blog post goes here.
    </textarea><br />
    <!-- The elements after this will be ignored -->
    <input type="submit" name="submit" value="Upload to Amazon S3" />
```

```
</form>
...
</html>
```

Sample Request

This request assumes that the image uploaded is 117,108 bytes; the image data is not included.

```
POST / HTTP/1.1
Host: johnsmith.s3.amazonaws.com
User-Agent: Mozilla/5.0 (Windows; U; Windows NT 5.1; en-US; rv:1.8.1.10)
Gecko/20071115 Firefox/2.0.0.10
Accept: text/xml,application/xml,applica
tion/xhtml+xml,text/html;q=0.9,text/plain;q=0.8,image/png,*/*;q=0.5
Accept-Language: en-us, en; q=0.5
Accept-Encoding: gzip, deflate
Accept-Charset: ISO-8859-1,utf-8;q=0.7,*;q=0.7
Keep-Alive: 300
Connection: keep-alive
Content-Type: multipart/form-data; boundary=178521717625888
Content-Length: 118635
-178521717625888
Content-Disposition: form-data; name="key"
ser/eric/NewEntry.html
--178521717625888
Content-Disposition: form-data; name="acl"
public-read
--178521717625888
Content-Disposition: form-data; name="success_action_redirect"
http://johnsmith.s3.amazonaws.com/new_post.html
--178521717625888
Content-Disposition: form-data; name="Content-Type"
text/html
--178521717625888
Content-Disposition: form-data; name="x-amz-meta-uuid"
14365123651274
--178521717625888
Content-Disposition: form-data; name="x-amz-meta-tag"
Interesting Post
--178521717625888
Content-Disposition: form-data; name="AWSAccessKeyId"
15B4D3461F177624206A
--178521717625888
Content-Disposition: form-data; name="Policy"
eyAiZXhwaXJhdGlvbiI6ICIyMDA3LTEyLTAxVDEyOjAwOjAwLjAwMFoiLAogICJjb25kaXRpb25zI
jogWwogICAgeyJidWNrZXQiOiAiam9obnNtaXRoIn0sCiAgICBbInN0YXJ0cy13aXRoIiwgIiRrZXkiL
CAidXNlci9lcmljLyJdLAogICAgeyJhY2wiOiAicHVibGljLXJlYWQifSwKICAgIH
sic3VjY2Vzc19hY3Rpb25fcmVkaXJ1Y3Qi0iAiaHR0cDovL2pvaG5zbWl0aC5zMy5hb
WF6b25hd3MuY29tL25ld19wb3N0Lmh0bWwifSwKICAgIFsiZXEiLCAiJENvbnRlbnQtVHlwZSIs
```

```
ICJ0ZXh0L2h0bWwiXSwKICAgIHsieClhbXotbWV0YS1ldWlkIjogIjE0MzYlMTIzN
jUxMjc0In0sCiAgICBbInN0YXJ0cyl3aXRoIiwgIiR4LWFteiltZXRhLXRhZyIsICIiXQogIF0KfQo=
--178521717625888
Content-Disposition: form-data; name="Signature"

qA7FWXKq6VvU68l19KdveTlcWgE=
--178521717625888
Content-Disposition: form-data; name="file"

...content goes here...
--178521717625888
Content-Disposition: form-data; name="submit"

Upload to Amazon S3
--178521717625888--
```

Sample Response

```
HTTP/1.1 303 Redirect
x-amz-request-id: 1AEE782442F35865
x-amz-id-2: cxzFLJRatFHy+NGtaDFRR8YvI9BHmgLxjvJzNiGGICARZ/mVXHj7T+qQKhdpzHFh
Content-Type: application/xml
Date: Wed, 14 Nov 2007 21:21:33 GMT
Connection: close
Location: http://johnsmith.s3.amazonaws.com/new_post.html?bucket=johns
mith&key=user/eric/NewEntry.html&etag=40c3271af26b7f1672e41b8a274d28d4
Server: AmazonS3
```

POST with Adobe Flash

This section describes how to use POST with Adobe Flash.

Adobe Flash Player Security

By default, the Adobe Flash Player security model prohibits Adobe Flash Players from making network connections to servers outside the domain that serves the SWF file.

To override the default, you must upload a public-readable crossdomain.xml file to the bucket that will accept POST uploads. Following is a sample crossdomain.xml file.

```
<?xml version="1.0"?>
<!DOCTYPE cross-domain-policy SYSTEM
"http://www.macromedia.com/xml/dtds/cross-domain-policy.dtd">
<cross-domain-policy>
<allow-access-from domain="*" secure="false" />
</cross-domain-policy>
```



Note

For more information about the Adobe Flash security model, go to the Adobe web site.

Adding the crossdomain.xml file to your bucket allows any Adobe Flash Player to connect to the crossdomain.xml file within your bucket. However, it does not grant access to the actual Amazon S3 bucket.

Adobe Flash Considerations

The FileReference API in Adobe Flash adds the Filename form field to the POST request. When building Adobe Flash applications that upload to Amazon S3 using the FileReference API, include the following condition in your policy:

```
['starts-with', '$Filename', '']
```

Some versions of the Adobe Flash Player do not properly handle HTTP responses that have an empty body. To configure POST to return a response that does not have an empty body, set success_action_status to 201. When set, Amazon S3 returns an XML document with a 201 status code. For information on the content of the XML document, see POST Object. For information on form fields, go to Form Fields.

Working with Amazon S3 Buckets

Topics

- Bucket Restrictions and Limitations (p. 83)
- Bucket Configuration Options (p. 84)
- Managing Bucket Website Configuration (p. 86)
- Requester Pays Buckets (p. 95)
- Buckets and Access Control (p. 99)
- Billing and Reporting of Buckets (p. 99)
- Bucket Configuration Errors (p. 99)

Every object stored in Amazon S3 is contained in a bucket. Buckets partition the namespace of objects stored in Amazon S3 at the top level. Within a bucket, you can use any names for your objects, but bucket names must be unique across all of Amazon S3.

Buckets are similar to Internet domain names. Just as Amazon is the only owner of the domain name Amazon.com, only one person or organization can own a bucket within Amazon S3. Once you create a uniquely named bucket in Amazon S3, you can organize and name the objects within the bucket in any way you like and the bucket will remain yours for as long as you like and as long as you have the Amazon S3 account.

The similarities between buckets and domain names is not a coincidence—there is a direct mapping between Amazon S3 buckets and subdomains of s3.amazonaws.com. Objects stored in Amazon S3 are addressable using the REST API under the domain <code>bucketname.s3.amazonaws.com</code>. For example, if the object homepage.html is stored in the Amazon S3 bucket mybucket its address would be http://mybucket.s3.amazonaws.com/homepage.html. For more information, see Virtual Hosting of Buckets (p. 59).

To determine whether a bucket name exists using REST, use <code>HEAD</code>, specify the name of the bucket, and set <code>max-keys</code> to 0. To determine whether a bucket name exists using SOAP, use <code>ListBucket</code> and set <code>MaxKeys</code> to 0. A NoSuchBucket response indicates that the bucket is available, a AccessDenied response indicates that someone else owns the bucket, and a Success response indicates that you own the bucket or have permission to access it.

Bucket Restrictions and Limitations

A bucket is owned by the AWS account (identified by AWS Access Key ID) that created it. Each AWS account can own up to 100 buckets at a time. Bucket ownership is not transferable. However, if a bucket is empty, it can be deleted and its name can be reused.



Note

If you are using Amazon DevPay, each of your customers can have up to 100 buckets for each Amazon DevPay product they use. For more information, see Using Amazon DevPay with Amazon S3 (p. 304).

To comply with Amazon S3 requirements, bucket names:

- Can contain lowercase letters, numbers, periods (.), underscores (_), and dashes (-)
- · Must start with a number or letter
- · Must be between 3 and 255 characters long
- Must not be formatted as an IP address (e.g., 192.168.5.4)

To conform with DNS requirements, we recommend following these additional guidelines when creating buckets:

- Bucket names should not contain underscores (_)
- Bucket names should be between 3 and 63 characters long
- · Bucket names should not end with a dash
- Bucket names cannot contain two, adjacent periods
- Bucket names cannot contain dashes next to periods (e.g., "my-.bucket.com" and "my.-bucket" are invalid)



Note

Buckets with names containing uppercase characters are not accessible using the virtual hosted-style request (e.g., http://yourbucket.s3.amazonaws.com/yourobject)

If you create a bucket using $\c Create Bucket Configuration >$, you must follow the DNS guidelines.

If you create a bucket using <CreateBucketConfiguration>, applications that access your bucket must be able to handle 307 redirects. For more information, see Request Redirection and the REST API (p. 296).

When using virtual hosted-style buckets with SSL, the SSL wild card certificate only matches buckets that do not contain periods. To work around this, use HTTP or write your own certificate verification logic.

There is no limit to the number of objects that can be stored in a bucket and no variation in performance when using many buckets or just a few. You can store all of your objects in a single bucket or organize them across several buckets.

Buckets cannot be nested, meaning buckets cannot be created within buckets.

The high availability engineering of Amazon S3 is focused on get, put, list, and delete operations. Because bucket operations work against a centralized, global resource space, it is not appropriate to make bucket create or delete calls on the high availability code path of your application. It is better to create or delete buckets in a separate initialization or setup routine that you run less often.



Note

If your application automatically creates buckets, choose a bucket naming scheme that is unlikely to cause naming conflicts. Additionally, make sure your application has logic to choose a different bucket name if a bucket name is already taken.

Bucket Configuration Options

When creating buckets, you can take advantage of additional Amazon S3 features by attaching the <CreateBucketConfiguration> XML body to a PUT Bucket request. Currently, you can select a location constraint. For more information, see Buckets and Regions (p. 84).

Buckets created with <CreateBucketConfiguration> are subject to additional restrictions:

- You cannot make a request to a bucket created with <CreateBucketConfiguration> using a path-style request; you must use the virtual hosted-style request. For more information, see Virtual Hosting of Buckets (p. 59).
- You must follow additional bucket naming restrictions. For more information, see Bucket Restrictions and Limitations (p. 83).

Buckets and Regions

You can choose the geographical Region where Amazon S3 will store the buckets you create. You might choose a Region to optimize latency, minimize costs, or address regulatory requirements. For example, if you reside in Europe, you will probably find it advantageous to create buckets in the EU (Ireland) Region.



Important

The SOAP API does not support geographical constraints.

Objects stored in a Region never leave that Region unless you explicitly transfer them to another Region. For example, objects stored in the EU (Ireland) Region never leave it.

Amazon S3 supports the following Regions:

- US Standard—Uses Amazon S3 servers in the United States
 This is the default Region. The US Standard Region automatically routes requests to facilities in Northern Virginia or the Pacific Northwest using network maps. To use this region, select US Standard as the region when creating a bucket in the console. The US Standard Region provides eventual consistency for all requests.
- US West (Northern California) Region—Uses Amazon S3 servers in Northern California
 To use this Region, choose Northern California as the Region when creating the bucket in the AWS
 Management Console.
 - In Amazon S3, the US West (Northern California) Region provides read-after-write consistency for PUTS of new objects in your Amazon S3 bucket and eventual consistency for overwrite PUTS and DELETES.
- EU (Ireland) Region—Uses Amazon S3 servers in Ireland
 To use this Region, choose Ireland as the Region when creating the bucket in the AWS Management Console. In Amazon S3, the EU (Ireland) Region provides read-after-write consistency for PUTS of new objects in your Amazon S3 bucket and eventual consistency for overwrite PUTS and DELETES.
- Asia Pacific (Singapore) Region—Uses Amazon S3 servers in Singapore.

Amazon Simple Storage Service Developer Guide Buckets and Regions

To use this Region, choose Singapore as the Region when creating the bucket in the AWS Management Console. In Amazon S3, the Asia Pacific (Singapore) Region provides read-after-write consistency for PUTS of new objects in your Amazon S3 bucket and eventual consistency for overwrite PUTS and DELETES.

Asia Pacific (Tokyo) Region—Uses Amazon S3 servers in Tokyo.
 To use this Region, choose Tokyo as the Region when creating the bucket in the AWS Management Console. In Amazon S3, the Asia Pacific (Tokyo) Region provides read-after-write consistency for PUTS of new objects in your Amazon S3 bucket and eventual consistency for overwrite PUTS and DELETES.

Regions are set at the bucket level. You specify a Region using the <code>LocationConstraint</code> bucket parameter. If you do not specify a Region, Amazon S3 hosts your buckets on servers in the US Standard Region.



Important

If you use a Region-specific endpoint to create a bucket, you *must* set the *LocationConstraint* bucket parameter to the same Region. For more information about Region-specific endpoints, see Request Endpoints (p. 12).

How to Specify a Bucket's Region

Use the following process to specify a bucket's Region.

Specifying a Bucket's Region

- In a bucket creation request, set the LocationContraint parameter to a specific Region, for example, CreateBucketConfiguration.LocationConstraint=us-west-1
- Optionally, when creating a bucket in the Northern California Region, you can also use a Region-specific endpoint in the request to create the bucket. For example, to match the Region specified in step 1, you would use the endpoint, https://s3-us-west-1.amazonaws.com (or http://s3-us-west-1.amazonaws.com).

Using the Region-specific endpoint avoids the latency caused by the redirection of requests from US Standard to the Northern California Region. For more information, see Redirection (p. 86). (The EU (Ireland) Region does not have a Region-specific endpoint.)



Important

Even if you use a Region-specific endpoint in a request to create a Northern California Region bucket, you must set the value of <code>LocationConstraint</code> to the same Region.

Bucket Access

To access Amazon S3 buckets and objects that were created using CreateBucketConfiguration, you can use the virtual hosted-style request in all Regions. For example:

http://yourbucket.s3.amazonaws.com/yourobject

To use the path-style request, the bucket must be in the US Classic Region, or the bucket must be in the same Region as the endpoint in the request. For example:

http://s3.amazonaws.com/yourbucket/yourobject

Redirection

Amazon supports two types of redirects: temporary and permanent.

Temporary redirects automatically redirect users that do not have DNS information for the requested bucket. This occurs because DNS changes take time to propagate through the Internet. For example, if a user creates a bucket with a location constraint and immediately stores an object in the bucket, information about the bucket might not distribute throughout the Internet. Because the bucket is a sub domain of s3.amazonaws.com, Amazon S3 redirects it to the correct Amazon S3 location.

You can remove this (short lived) redirection latency by using a Region-specific endpoint in the bucket creation request. The <code>LocationConstraint</code> bucket parameter specifies the Region where the bucket will reside. Using the Region-specific endpoint is optional. The only Region you can do this in is US-West. For more information, see How to Specify a Bucket's Region (p. 85).

Transferring a Bucket's Contents to Another Region

Use the following process to transfer your bucket from one Region to another.

To transfer a bucket to another Region

- 1 Create a new Amazon S3 bucket in the Region you wish to transfer your data to.
- 2 Use the copy operation to transfer each of your objects from the source Region to the target Region. Bandwidth charges apply for this transfer. For more information, go to COPY Object.

Managing Bucket Website Configuration

Topics

- Managing Websites with the AWS Management Console (p. 86)
- Managing Websites with the AWS SDK for Java (p. 87)
- Managing Websites with the AWS SDK for .NET (p. 90)
- Managing Websites with the AWS SDK for PHP (p. 94)
- Managing Websites with the REST API (p. 95)

You can host static websites in Amazon S3 by adding website configuration to your bucket. You do this by adding a website subresource describing the configuration information, such as the index document name and the custom error document name. There are several ways you can manage your bucket's website configuration. AWS Management Console enables you to manage configuration without writing any code. You can programmatically create, update and delete the website configuration using the AWS SDK. The SDK provides wrapper classes around the Amazon S3 REST API; and if your application requires it, you can send the REST API requests directly from your application.

Managing Websites with the AWS Management Console

Amazon S3 tab on the console enables you to manage bucket properties. The bucket properties pane provides the following **Website** properties tab for you to manage your bucket's website configuration.

Amazon Simple Storage Service Developer Guide Managing Websites with the AWS SDK for Java



To configure your bucket as a website, you must select the **Enabled** check box and provide an index document name in the **Index Document Suffix** field. You can optionally provide the **Error Document Key**. This is the custom error document you can provide with user-friendly information. If you don't provide this document, Amazon S3 returns predefined error documents when an error occur. For more information, see Custom Error Document Support (p. 288).

If you clear the **Enabled** box, the bucket is no longer a website and cannot be accessed via the website endpoints (see Website Endpoints (p. 285)). However, the bucket is still accessible via the REST endpoint.

Managing Websites with the AWS SDK for Java

The following tasks guide you through using the Java classes to manage website configuration to your bucket. For more information about the Amazon S3 website feature, see Hosting Websites on Amazon S3 (p. 283).

Managing Website Configuration

1	Create an instance of the AmazonS3 class by providing your AWS credentials.
2	To add website configuration to a bucket, execute the AmazonS3.setBucketWebsiteConfiguration method. You need to provide the bucket name and the website configuration information including the index document and the error document names. You must provide the index document, however, the error document is optional. You provide website configuration information by creating a BucketWebsiteConfiguration object.
	To retrieve website configuration, execute the AmazonS3.getBucketWebsiteConfiguration method by providing the bucket name.
	To delete your bucket website configuration, execute the AmazonS3.deleteBucketWebsiteConfiguration method by providing the bucket name. After you remove the website configuration, the bucket is no longer available via the website endpoint. For more information, see see Website Endpoints (p. 285).

The following Java code sample demonstrates the preceding tasks.

Amazon Simple Storage Service Developer Guide Managing Websites with the AWS SDK for Java

Example

The following Java code example adds a website configuration to the specified bucket, retrieves it and deletes the website configuration. For instructions on how to create and test a working sample, see Testing the Java Code Examples (p. 327).

```
import java.io.IOException;
import com.amazonaws.AmazonClientException;
import com.amazonaws.AmazonServiceException;
import com.amazonaws.auth.BasicAWSCredentials;
import com.amazonaws.services.s3.AmazonS3;
import com.amazonaws.services.s3.AmazonS3Client;
import com.amazonaws.services.s3.model.BucketWebsiteConfiguration;
public class S3Sample {
private static String bucketName = "mvphp1";
private static String indexDoc = "index.html";
private static String errorDoc = "error.html";
public static void main(String[] args) throws IOException {
       AmazonS3 s3Client = new AmazonS3Client(new PropertiesCredentials(
          S3Sample.class.getResourceAsStream("AwsCredentials.properties")));
        try {
        // Get existing website configuration, if any.
           getWebsiteConfig(s3Client);
      // Set new website configuration.
     s3Client.setBucketWebsiteConfiguration(bucketName,
        new BucketWebsiteConfiguration(indexDoc, errorDoc));
      // Verify (Get website configuration again).
           getWebsiteConfig(s3Client);
            // Delete
            s3Client.deleteBucketWebsiteConfiguration(bucketName);
         // Verify (Get website configuration again)
              getWebsiteConfig(s3Client);
        } catch (AmazonServiceException ase) {
           System.out.println("Caught an AmazonServiceException, which" +
              " means your request made it " +
                    "to Amazon S3, but was rejected with an error response" +
                    " for some reason.");
           System.out.println("Error Message:
                                                  " + ase.getMessage());
           System.out.println("HTTP Status Code: " + ase.getStatusCode());
           System.out.println("AWS Error Code: " + ase.getErrorCode());
           System.out.println("Error Type:
                                                  " + ase.getErrorType());
                                                  " + ase.getRequestId());
           System.out.println("Request ID:
        } catch (AmazonClientException ace) {
           System.out.println("Caught an AmazonClientException, which means"+
              " the client encountered " +
                    "a serious internal problem while trying to " +
```

```
"communicate with Amazon S3, " +
                   "such as not being able to access the network.");
           System.out.println("Error Message: " + ace.getMessage());
   }
private static BucketWebsiteConfiguration getWebsiteConfig(
                                              AmazonS3 s3Client) {
 System.out.println("Get website config");
 // 1. Get website config.
 BucketWebsiteConfiguration bucketWebsiteConfiguration =
    s3Client.getBucketWebsiteConfiguration(bucketName);
 if (bucketWebsiteConfiguration == null)
 System.out.println("No website config.");
 else
 {
      System.out.println("Index doc:" +
       bucketWebsiteConfiguration.getIndexDocumentSuffix());
      System.out.println("Error doc:" +
       bucketWebsiteConfiguration.getErrorDocument());
return bucketWebsiteConfiguration;
```

Managing Websites with the AWS SDK for .NET

The following tasks guide you through using the .NET classes to manage website configuration on your bucket. For more information about the Amazon S3 website feature, see Hosting Websites on Amazon S3 (p. 283).

Managing Bucket Website Configuration

1	Create an instance of the AmazonS3 class by providing your AWS credentials.
2	To add website configuration to a bucket, execute the AmazonS3.PutBucketWebsite method. You need to provide the bucket name and the website configuration information including the index document and the error document names. You must provide the index document, however, the error document is optional. You provide this information by creating a PutBucketWebsiteRequest object.
	To retrieve website configuration, execute the AmazonS3.GetBucketWebsite method by providing the bucket name.
	To delete your bucket website configuration, execute the AmazonS3.DeleteBucketWebsite method by providing the bucket name. After you remove the website configuration, the bucket is no longer available via the website endpoint. For more information, see see Website Endpoints (p. 285).

The following C# code sample demonstrates the preceding tasks.

```
AmazonS3 client;
client = Amazon.AWSClientFactory.CreateAmazonS3Client(
```

Amazon Simple Storage Service Developer Guide Managing Websites with the AWS SDK for .NET

```
accessKeyID, secretAccessKeyID);
// Add website configuration.
PutBucketWebsiteRequest putRequest =
  new PutBucketWebsiteRequest()
        .WithBucketName(bucketName)
        .WithWebsiteConfiguration(new WebsiteConfiguration()
        .WithIndexDocumentSuffix(indexDocumentSuffix)
        .WithErrorDocument(errorDocument));
client.PutBucketWebsite(putRequest);
// Get bucket website configuration.
GetBucketWebsiteRequest getRequest =
  new GetBucketWebsiteRequest()
     .WithBucketName(bucketName);
GetBucketWebsiteResponse getResponse =
 client.GetBucketWebsite(getRequest);
// Print configuration data.
Console.WriteLine("Index document: {0}", getResponse.WebsiteConfiguration.Index
DocumentSuffix);
Console.WriteLine("Error document: {0}", getResponse.WebsiteConfiguration.Error
Document);
// Delete website configuration.
DeleteBucketWebsiteRequest deleteRequest =
   new DeleteBucketWebsiteRequest()
        .WithBucketName(bucketName);
client.DeleteBucketWebsite(deleteRequest);
```

Example

The following C# code example adds a website configuration to the specified bucket. The configuration specifies both the index document and the error document names. For instructions on how to create and test a working sample, see Testing the .NET Code Examples (p. 328).

```
using System;
using System.Configuration;
using System.Collections.Specialized;
using Amazon.S3;
using Amazon.S3.Model;
namespace s3.amazon.com.docsamples.addwebsiteconfiguration
    class S3Sample
        static string bucketName
                                          = "*** Provide existing bucket name
        static string indexDocumentSuffix = "*** Provide index document name
                                          = "*** Provide error document name
        static string errorDocument
        static AmazonS3 client;
        public static void Main(string[] args)
            if (checkRequiredFields())
                NameValueCollection appConfig =
                    ConfigurationManager.AppSettings;
                string accessKeyID = appConfig["AWSAccessKey"];
                string secretAccessKeyID = appConfig["AWSSecretKey"];
                using (client = Amazon.AWSClientFactory.CreateAmazonS3Client(
                    accessKeyID, secretAccessKeyID))
                   AddWebsiteConfig(bucketName, indexDocumentSuffix, errorDoc
ument);
                }
            Console.WriteLine("Press any key to continue...");
            Console.ReadKey();
        static void AddWebsiteConfig(string bucketName,
                                     string indexDocumentSuffix,
                                     string errorDocument)
        {
            try
                PutBucketWebsiteRequest putRequest =
                    new PutBucketWebsiteRequest()
                    .WithBucketName(bucketName)
                    .WithWebsiteConfiguration(new WebsiteConfiguration()
                        .WithIndexDocumentSuffix(indexDocumentSuffix)
                        .WithErrorDocument(errorDocument));
```

```
client.PutBucketWebsite(putRequest);
           catch (AmazonS3Exception amazonS3Exception)
               if (amazonS3Exception.ErrorCode != null &&
                   (amazonS3Exception.ErrorCode.Equals("InvalidAccessKeyId")
                   | amazonS3Exception.ErrorCode.Equals("InvalidSecurity")))
                   Console.WriteLine("Check the provided AWS Credentials.");
                   Console.WriteLine(
                       "Sign up for service at http://aws.amazon.com/s3");
               }
               else
                   Console.WriteLine(
                      "Error: {0}, occurred when adding website configuration.
Message: '{1}",
                     amazonS3Exception.ErrorCode, amazonS3Exception.Message);
       static bool checkRequiredFields()
           NameValueCollection appConfig = ConfigurationManager.AppSettings;
           if (string.IsNullOrEmpty(appConfig["AWSAccessKey"]))
               Console.WriteLine(
                   "AWSAccessKey was not set in the App.config file.");
               return false;
           if (string.IsNullOrEmpty(appConfig["AWSSecretKey"]))
               Console.WriteLine(
                   "AWSSecretKey was not set in the App.config file.");
               return false;
           if (string.IsNullOrEmpty(bucketName))
               Console.WriteLine("The variable bucketName is not set.");
               return false;
           return true;
   }
```

Managing Websites with the AWS SDK for PHP

The following tasks guide you through using the PHP classes to manage website configuration of your bucket. For more information about the Amazon S3 website feature, see Hosting Websites on Amazon S3 (p. 283).

Managing Bucket Website Configuration

1	Create an instance of the AmazonS3 class by providing your AWS credentials.
2	To configure a bucket as a website, execute the AmazonS3.create_website_config method. You need to provide the bucket name and the website configuration information including the index document and the error document names. If you don't provide these document names, this method adds the index.html and error.html default names to the website configuration. You must verify that these documents are present in the bucket.
	To retrieve existing bucket website configuration, execute the AmazonS3.get_website_config method by passing the bucket name as a parameter.
	To delete website configuration from a bucket, execute the AmazonS3.delete_website_config method by passing the bucket name as a parameter. If you remove the website configuration, the bucket is no longer accessible from the website endpoints.

The following PHP code sample demonstrates the preceding tasks.

```
<?php
require_once '../aws-sdk-for-php/sdk.class.php';
header('Content-Type: text/plain; charset=utf-8');
$bucket = '*** Provide bucket name ***';
$indexDocument = '*** Provide index document name ****';
$errorDocument = '*** Provide error document name ***';
// Instantiate the class
$s3 = new AmazonS3();
// 1) Add website config. to bucket.
$response = $s3->create_website_config($bucket,
                                          'indexDocument' => $indexDocument,
                                          'errorDocument' => $errorDocument));
// 2) Retrieve website configuration.
$response = $s3->get_website_config($bucket);
header('Content-Type: text/plain; charset=utf-8');
// 3) Delete website configuration.
$response = $s3->delete_website_config($bucket);
```

Example

The following PHP code example first adds a website configuration to the specified bucket. The create_website_config method explicitly provides the index document and error document names. The sample also retrieves the website configuration and prints the response. For more information about the Amazon S3 website feature, see Hosting Websites on Amazon S3 (p. 283). For instructions on how to create and test a working sample, see Using the AWS SDK for PHP (p. 329).

```
<?php
require_once '../aws-sdk-for-php/sdk.class.php';
header('Content-Type: text/plain; charset=utf-8');
$bucket = '*** Provide bucket name ***';
$indexDocument = '*** Provide index document name ****';
$errorDocument = '*** Provide error document name ***';
// Instantiate the class
$s3 = new AmazonS3();
// 1) Add website config. to bucket.
$response = $s3->create_website_config($bucket,
                                       arrav(
                                         'indexDocument' => $indexDocument,
                                          'errorDocument' => $errorDocument));
// Success?
var_dump($response->isOK());
// 2) Retrieve website configuration.
$response = $s3->get_website_config($bucket);
header('Content-Type: text/plain; charset=utf-8');
print_r($response);
// 3) Delete website configuration.
$response = $s3->delete_website_config($bucket);
var_dump($response->isOK());
```

Managing Websites with the REST API

Topics

You can use the AWS Management Console or the AWS SDK to configure a bucket as a website. However, if your application requires it, you can send REST requests directly. For more information, see the following sections in the Amazon Simple Storage Service API Reference.

- PUT Bucket website
- · GET Bucket website
- DELETE Bucket website

Requester Pays Buckets

In general, bucket owners pay for all Amazon S3 storage and data transfer costs associated with their bucket. A bucket owner, however, can configure a bucket to be a Requester Pays bucket. With Requester Pays buckets, the requester instead of the bucket owner pays the cost of the request and the data download from the bucket. The bucket owner always pays the cost of storing data.

Typically, you configure buckets to be Requester Pays when you want to share data but not incur charges associated with others accessing the data. You might, for example, use Requester Pays buckets when making available large data sets, such as zip code directories, reference data, geospatial information, or web crawling data.



Important

If you enable Requester Pays on a bucket, anonymous access to that bucket is not allowed.

You must authenticate all requests involving Requester Pays buckets. The request authentication enables Amazon S3 to identify and charge the requester for their use of the Requester Pays bucket.

After you configure a bucket to be a Requester Pays bucket, requesters must include x-amz-request-payer in their requests either in the header, for POST and GET requests, or as a parameter in a REST request to show that they understand that they will be charged for the request and the data download.

Requester Pays buckets do not support the following.

- Anonymous requests
- BitTorrent
- SOAP requests
- You cannot use a Requester Pays bucket as the target bucket for end user logging, or vice versa.
 However, you can turn on end user logging on a Requester Pays bucket where the target bucket is a non Requester Pays bucket.

Setting the requestPayment Bucket Configuration

The bucket owner and only the bucket owner can set the <code>RequestPaymentConfiguration.payer</code> configuration value of a bucket to <code>BucketOwner</code>, the default, or <code>Requester</code>. Setting the <code>requestPayment</code> resource is optional. If you don't, the bucket, by default, is a non-Requester Pays bucket.

You use the value, BucketOwner, to revert Requester Pays buckets to regular buckets. Typically, you would use BucketOwner when uploading data to the Amazon S3 bucket, then set the value to Requester before publishing the objects in the bucket.

To set requestPayment

• Use a PUT request to set the Payer value to Requester on a specified bucket.

```
PUT ?requestPayment HTTP/1.1
Host: [BucketName].s3.amazonaws.com
Content-Length: 173
Date: Wed, 01 Mar 2009 12:00:00 GMT
Authorization: AWS [Signature]

<RequestPaymentConfiguration xmlns="http://s3.amazonaws.com/doc/2006-03-01/">
<Payer>Requester</Payer>
</RequestPaymentConfiguration>
```

If the request succeeds, Amazon S3 returns a response similar to the following.

Amazon Simple Storage Service Developer Guide Retrieving requestPayment Configuration

```
HTTP/1.1 200 OK
x-amz-id-2: [id]
x-amz-request-id: [request_id]
Date: Wed, 01 Mar 2009 12:00:00 GMT
Content-Length: 0
Connection: close
Server: AmazonS3
x-amz-request-charged:requester
```

Notice that you can only set Requester Pays at the bucket level; you cannot set Requester Pays for specific objects within the bucket.

You can freely configure a bucket to be BucketOwner or Requester at any time. Realize, however, that there might be a small delay, on the order of minutes, for the configuration value to take effect.



Note

Bucket owners who give out pre-signed URLs should think twice before configuring a bucket to be Requester Pays, especially if the URL has a very long expiry. The bucket owner is charged each time the requester uses pre-signed URLs that use the bucket owner's credentials.

Retrieving requestPayment Configuration

You can determine the Payer value set on a bucket by requesting the resource requestPayment.

To return the requestPayment resource

• Use a GET request to obtain the requestPayment resource, as shown in the following request.

```
GET ?requestPayment HTTP/1.1

Host: [BucketName].s3.amazonaws.com

Date: Wed, 01 Mar 2009 12:00:00 GMT

Authorization: AWS [Signature]
```

If the request succeeds, Amazon S3 returns a response similar to the following.

```
HTTP/1.1 200 OK
x-amz-id-2: [id]
x-amz-request-id: [request_id]
Date: Wed, 01 Mar 2009 12:00:00 GMT
Content-Type: [type]
Content-Length: [length]
Connection: close
Server: AmazonS3

<?xml version="1.0" encoding="UTF-8"?>
<RequestPaymentConfiguration xmlns="http://s3.amazonaws.com/doc/2006-03-01/">
<Payer>RequestPaymentConfiguration>
```

This response shows that the payer value is set to Requester.

Downloading Objects in Requester Pays Buckets

Because requesters are charged for downloading data from Requester Pays buckets, the requests must contain a special parameter, x-amz-request-payer, which demonstrates the requester knows he or she will be charged for the download. To access objects in Requester Pays buckets, requests must include one of the following.

- ullet For GET and POST requests, include x-amz-request-payer : requester in the header
- For signed URLs, include x-amz-request-payer=requester in the request

If the request succeeds and the requester is charged, the response includes the header x-amz-request-charged:requester. If x-amz-request-payer is not in the request, Amazon S3 returns a 403 error and charges the bucket owner for the request.



Note

Bucket owners do not need to add *x-amz-request-payer* to their requests.

Make sure to include x-amz-request-payer and its value in your signature calculation. For more information, see Constructing the CanonicalizedAmzHeaders Element (p. 51).

To download objects from a Requester Pays bucket

 Use a GET request to download an object from a Requester Pays bucket, as shown in the following request.

```
GET / [destinationObject] HTTP/1.1
Host: [BucketName].s3.amazonaws.com
x-amz-request-payer: requester
Date: Wed, 01 Mar 2009 12:00:00 GMT
Authorization: AWS [Signature]
```

If the GET request succeeds and the requester is charged, the response includes x-amz-request-charged:requester.

Amazon S3 can return Access Denied errors for requests trying to get objects from Requester Pays buckets. For more information, go to ErrorCodeList.

DevPay and Requester Pays

You can use Amazon DevPay to sell the content stored in your Requester Pays bucket. For more information, go to "Using Amazon S3 Requester Pays with DevPay," in the Using Amazon S3 Requester Pays with DevPay.

Charge Details

The charge for successful Requester Pays requests is straight forward: the requester pays for data transfer and the request; the bucket owner pays for the data storage. However, the bucket owner is charged for the request if:

• The requester doesn't include the parameter x-amz-request-payer in the header (GET or POST) or as a parameter (REST) in the request (HTTP code 403)

Amazon Simple Storage Service Developer Guide Buckets and Access Control

- Request authentication fails (HTTP code 403)
- The request is anonymous (HTTP code 403)
- The request is a SOAP request

Buckets and Access Control

Each bucket has an associated access control policy. This policy governs the creation, deletion and enumeration of objects within the bucket. For more information, see Access Control (p. 204).

Billing and Reporting of Buckets

Fees for object storage and network data transfer are always billed to the owner of the bucket that contains the object unless the bucket was created as a Requester Pays bucket.

The reporting tools available at the Amazon Web Services developer portal organize your Amazon S3 usage reports by bucket. For more information, go to Amazon S3 Pricing page.

Bucket Configuration Errors

The following list shows the errors Amazon S3 can return in response to bucket configuration requests.

- MalformedXML
- MissingRequestBodyError

Working with Amazon S3 Objects

Topics

- Object Key and Metadata (p. 101)
- Object Subresources (p. 101)
- Object Versioning (p. 102)
- Operations on Objects (p. 105)
- Getting Objects (p. 109)
- Uploading Objects (p. 123)
- Copying Objects (p. 175)
- Listing Object Keys (p. 193)

Amazon S3 is a simple key, value store designed to store as many objects as you want. You store these objects in one or more buckets. An object consists of the following:

- **Key**—The name that you assign to an object. You use the object key to retrieve the object. For more information, see Object Key and Metadata (p. 101)
- Version ID—Within a bucket, a key and version ID uniquely identify an object.
 The version ID is a string that Amazon S3 generates when you add an object to a bucket. For more information, see Object Versioning (p. 102).
- Value—The content that you are storing.
 An object value can be any sequence of bytes. Objects can range from zero to 5 TB in size. For more information, see Uploading Objects (p. 123).
- **Metadata**—A set of name-value pairs with which you can store information regarding the object. You can assign metadata, referred to as user-defined metadata, to your objects in Amazon S3. Amazon S3 also assigns system-metadata to these objects, which it uses for managing objects. For more information, see Object Key and Metadata (p. 101).
- **Subresources**—Amazon S3 uses the subresource mechanism to store object-specific additional information.
 - Because subresources are subordinates to objects, they are always associated with some other entity such as an object or a bucket. For more information, see Object Subresources (p. 101).
- Access Control Information—You can controls access to the objects you store in Amazon S3.

 Amazon S3 supports both the resource-based access control, such as an Access Control List (ACL) and bucket policies, and user-based access control. For more information, see Access Control (p. 204).

Object Key and Metadata

Each Amazon S3 object has data, a key, and metadata. When you create an object you specify the key name. This key name uniquely identifies the object in the bucket. For exmaple, in Amazon S3 console (see AWS Management Console), when you highlight a bucket, a list of objects in your bucket appear. These names are the object keys. The name for a key is a sequence of Unicode characters whose UTF-8 encoding is at most 1024 bytes long.

In addition to the key, each Amazon S3 object has metadata. It is a set of name-value pairs. There are two kinds of metadata: system metadata and user-defined metadata.

System-Defined Metadata

For each object stored in a bucket, Amazon S3 maintains a set of system metadata. Amazon S3 processes this system metadata as needed. For example, Amazon S3 maintains object creation date and size metadata and uses this information as part of object management.

User-Defined Metadata

When uploading an object, you can also assign metadata to the object. You provide this optional information as a name, value pair when you send a PUT or POST request to create the object. When uploading objects using the REST API the optional user-defined metadata names must begin with "x-amz-meta-" to distinguish them from other HTTP headers. When you retrieve the object using the REST API, this prefix is returned. When uploading objects using the SOAP API, the prefix is not required. When you retrieve the object using the SOAP API, the prefix is removed, regardless of which API you used to upload the object.

When metadata is retrieved through the REST API, Amazon S3 combines headers that have the same name (ignoring case) into a comma-delimited list. If some metadata contains unprintable characters, it is not returned. Instead, the "x-amz-missing-meta" header is returned with a value of the number of the unprintable metadata entries.

Each name, value pair must conform to US-ASCII when using REST and UTF-8 when using SOAP or browser-based uploads via POST.



Note

The PUT request header is limited to 8 KB in size. Within the PUT request header, the user-defined metadata is limited to 2 KB in size. User-defined metadata is a set of key-value pairs. The size of user-defined metadata is measured by taking the sum of the number of bytes in the UTF-8 encoding of each key and value.

Object Subresources

Amazon S3 defines a set of subresources associated with buckets and objects. Subresources are subordinates to objects; that is, subresources do not exist on their own, they are always associated with some other entity, such as an object or a bucket.

The following table lists the subresources associated with Amazon S3 objects.

Amazon Simple Storage Service Developer Guide Object Versioning

Subresource	Description
acl	Contains a list of grants identifying the grantees and the permissions granted. When you create an object, the acl identifies the object owner as having full control over the object. You can retrieve an object ACL or replace it with updated list of grants. Any update to an ACL requires you to replace the existing ACL. For more information about ACLs, see Using ACLs (p. 228)
torrent	Amazon S3 supports the BitTorrent protocol. Amazon S3 uses the torrent subresource to return the torrent file associated with the specific object. To retrieve a torrent file, you specify the torrent subresource in your GET request. Amazon S3 creates a torrent file and returns it. You can only retrieve the torrent subresource, you cannot create, update or delete the torrent subresource. For more information, see Using BitTorrent with Amazon S3 (p. 301).

Object Versioning

Versioning enables you to keep multiple versions of an object in one bucket. You must explicitly enable versioning on your bucket. By default versioning is disabled. Regardless of whether you have enabled versioning on your bucket or not, each object has a version ID. If you have not enabled versioning on your bucket, then Amazon S3 sets the version ID value null. If you have enabled versioning on your bucket, Amazon S3 assigns a unique version ID value for the object.



Versioning enables you to keep multiple versions of an object in one bucket, for example, my-image.jpg (version 111111) and my-image.jpg (version 222222). You might enable versioning to recover from unintended overwrites and deletions or to archive objects so that you can retrieve previous versions of them.



Note

The SOAP API does not support Versioning.

When you enable versioning on a bucket, existing objects, if any, in the bucket are unchanged: the version IDs (null), contents, and permissions remain the same.

Enabling and suspending versioning is done at the bucket level. When you enable versioning for a bucket, all objects added to it will have a unique version ID. Unique version IDs are randomly generated, Unicode, UTF-8 encoded, URL-ready, opaque strings that are at most 1024 bytes long. An example version ID is 3/L4kqtJlcpXroDTDmJ+rmSpXd3dIbrHY+MTRCxf3vjVBH40Nr8X8gdRQBpUMLUo. Only Amazon S3 generates version IDs. They cannot be edited.




Note

For simplicity, we will use much shorter IDs in all our examples.

When you PUT an object in a version-enabled bucket, the old version is not overwritten. The following figure shows that when a new version of photo.gif is PUT into a bucket that already contains an object


with the same name, the original object (ID = 111111) remains in the bucket, Amazon S3 generates a new version ID (121212), and adds the newer version to the bucket.



Versioning Enabled


This functionality prevents you from accidentally overwriting or deleting objects and affords you the opportunity to retrieve a previous version of an object.

When you DELETE an object, all versions remain in the bucket and Amazon S3 inserts a delete marker, as shown in the following figure.




The delete marker becomes the latest version of the object. By default, GET requests retrieve the most recently stored version. Performing a simple GET Object request when the latest version is a delete marker returns a 404 Not Found error, as shown in the following figure.


Amazon Simple Storage Service Developer Guide Object Versioning



You can, however, GET an older version of an object by specifying its version ID. In the following figure, we GET a specific object version, 111111. Amazon S3 returns that object version even though it's not the latest version.



You can permanently delete an object by specifying the version you want to delete. Only the owner of an Amazon S3 bucket can permanently delete a version. The following figure shows how <code>DELETE versionId</code> permanently deletes an object from a bucket and that Amazon S3 doesn't insert a delete marker.



You can add additional security by configuring a bucket to enable MFA (Multi-Factor Authentication) Delete. When you do, the bucket owner must include two forms of authentication in any request to delete a version or change the versioning state of the bucket. For more information, see MFA Delete (p. 263).

For more information, see Using Versioning (p. 262).

Operations on Objects

Amazon S3 enables you to store, retrieve and delete objects. You can retrieve an entire object or a portion of an object. If you have enabled versioning on your bucket, you can retrieve a specific version of the object. You can also retrieve a subresource associated with your object and update it where applicable. You can make a copy of your existing object. Depending on the object size, the following upload and copy related considerations apply:

- Uploading objects—You can upload objects of up to 5 GB in size in a single operation. For objects greater than 5 GB you must use the multipart upload API.
 Using the multipart upload API you can upload objects up to 5 TB each. For more information, see Uploading Objects Using Multipart Upload API (p. 134).
- Copying objects—The copy operation creates a copy of an object that is already stored in Amazon S3.

You can create a copy of your object up to 5 GB in size in a single atomic operation. However, for copying an object greater than 5 GB, you must use the multipart upload API. For more information, see Copying Objects (p. 175).

You can use the REST API (see Making Requests using the REST API (p. 45)) to work with objects or use one of the following AWS SDK libraries:

- · AWS SDK for Java
- · AWS SDK for .NET
- · AWS SDK for PHP

These libraries provide a high-level abstraction that makes working with objects easy. However, if your application requires, you can use the REST API directly.

Multipart Upload Overview

Topics

- Concurrent Multipart Upload Operations (p. 107)
- Multipart Upload and Pricing (p. 107)
- Quick Facts (p. 107)
- API Support for Multipart Upload (p. 108)
- Multipart Upload API and Permissions (p. 108)

The Multipart upload API enables you to upload large objects in parts. You can use this API to upload new large objects or make a copy of an existing object (see Operations on Objects (p. 105)).

Multipart uploading is a three-step process: You initiate the upload, you upload the object parts, and after you have uploaded all the parts, you complete the multipart upload. Upon receiving the complete multipart upload request, Amazon S3 constructs the object from the uploaded parts, and you can then access the object just as you would any other object in your bucket.

You can list of all your in-progress multipart uploads or get a list of the parts that you have uploaded for a specific multipart upload. Each of these operations is explained in this section.

Multipart Upload Initiation

When you send a request to initiate a multipart upload, Amazon S3 returns a response with an upload ID, which is a unique identifier for your multipart upload. You must include this upload ID whenever you upload parts, list the parts, complete an upload, or abort an upload. If you want to provide any metadata describing the object being uploaded, you must provide it in the request to initiate multipart upload.

Parts Upload

When uploading a part, in addition to the upload ID, you must specify a part number. You can choose any part number between 1 and 10,000. A part number uniquely identifies a part and its position in the object you are uploading. If you upload a new part using the same part number as a previously uploaded part, the previously uploaded part is overwritten. Whenever you upload a part, Amazon S3 returns an *ETag* header in its response. For each part upload, you must record the part number and the ETag value. You need to include these values in the subsequent request to complete the multipart upload.

Multipart Upload Completion (or Abort)

When you complete a multipart upload, Amazon S3 creates an object by concatenating parts in ascending order based on the part number. If any object metadata was provided in the *initiate multipart upload* request, Amazon S3 associates that metadata with the object. After a successful *complete* request, the parts no longer exist. Your *complete multipart upload* request must include the upload ID and a list of both part numbers and corresponding ETag values. Amazon S3 response includes an ETag that uniquely identifies the combined object data. This ETag will not necessarily be an MD5 hash of the object data. You can optionally abort the multipart upload. After aborting a multipart upload, you cannot upload any part using that upload ID again. All storage that any parts from the aborted multipart upload consumed is then freed. If any part uploads were in-progress, they can still succeed or fail even after you aborted. To free all storage consumed by all parts, you must abort a multipart upload only after all part uploads have completed.

Multipart Upload Listings

You can list the parts of a specific multipart upload or all in-progress multipart uploads. The list parts operation returns the parts information that you have uploaded for a specific multipart upload. For each list parts request, Amazon S3 returns the parts information for the specified multipart upload, up to a maximum of 1000 parts. If there are more than 1000 parts in the multipart upload, you must send a series

Amazon Simple Storage Service Developer Guide Multipart Upload Overview

of list part requests to retrieve all the parts. Note that the returned list of parts doesn't include parts that haven't completed uploading.



Note

Only use the returned listing for verification. You should not use the result of this listing when sending a *complete multipart upload* request. Instead, maintain your own list of the part numbers you specified when uploading parts and the corresponding ETag values that Amazon S3 returns.

Using the *list multipart uploads* operation, you can obtain a list of multipart uploads in progress. An in-progress multipart upload is an upload that you have initiated, but have not yet completed or aborted. Each request returns at most 1000 multipart uploads. If there are more than 1000 multipart uploads in progress, you need to send additional requests to retrieve the remaining multipart uploads.

Concurrent Multipart Upload Operations

In a distributed development environment, it is possible for your application to initiate several updates on the same object at the same time. Your application might initiate several multipart uploads using the same object key. For each of these uploads, your application can then upload parts and send a complete upload request to Amazon S3 to create the object. When the buckets have versioning enabled, completing a multipart upload always creates a new version. For buckets that do not have versioning enabled, it is possible that some other request received between the time when a multipart upload is initiated and when it is completed might take precedence.



Note

It is possible for some other request received between the time you initiated a multipart upload and completed it to take precedence. For example, if another operation deletes a key after you initiate a multipart upload with that key, but before you complete it, the complete multipart upload response might indicate a successful object creation without you ever seeing the object.

Multipart Upload and Pricing

Once you initiate a multipart upload, Amazon S3 retains all the parts until you either complete or abort the upload. Throughout its lifetime, you are billed for all storage, bandwidth, and requests for this multipart upload and its associated parts. If you abort the multipart upload, Amazon S3 deletes upload artifacts and any parts you have uploaded, and you are no longer billed for them. For more information on pricing, go to the Amazon S3 Pricing page.

Quick Facts

The following table provides multipart upload (see Multipart Upload Overview (p. 106)) core specifications.

Item	Specification
Maximum object size	5 TB
Maximum number of parts per upload	10,000
Part numbers	1 to 10,000 (inclusive)
Part size	5 MB to 5 GB, last part can be < 5 MB
Maximum number of parts returned for a list parts request	1000

Amazon Simple Storage Service Developer Guide Multipart Upload Overview

Item	Specification
Maximum number of multipart uploads returned in a list multipart uploads request	1000

API Support for Multipart Upload

You can use an AWS SDK to upload an object in parts. The following AWS SDK libraries support multipart upload:

- · AWS SDK for Java
- · AWS SDK for .NET
- · AWS SDK for PHP

These libraries provide a high level abstraction that makes uploading multipart objects easy. However, if your application requires, you can use the REST API directly. The following sections in the Amazon Simple Storage Service API Reference describe the REST API for multipart upload.

- · Initiate Multipart Upload
- Upload Part
- Upload Part (Copy)
- · Complete Multipart Upload
- Abort Multipart Upload
- List Parts
- List Multipart Uploads

Multipart Upload API and Permissions

An individual must have the necessary permissions to use the multipart upload operations. You can use ACLs, the bucket policy, or the user policy to grant individuals permissions to perform these operations. The following table lists the required permissions for various multipart upload operations when using ACLs, bucket policy, or the user policy.

Action	Required Permissions
Initiate Multipart Upload	You must be allowed to perform the s3:PutObject action on an object to initiate multipart upload. The bucket owner can allow other principals to perform the s3:PutObject action.
Upload Part	You must be allowed to perform the s3:PutObject action on an object to upload a part. Only the initiator of a multipart upload can upload parts. The bucket owner must allow the initiator to perform the s3:PutObject action on an object in order for the initiator to upload a part for that object.

Amazon Simple Storage Service Developer Guide Getting Objects

Action	Required Permissions
Upload Part (Copy)	You must be allowed to perform the s3:PutObject action on an object to upload a part. Because your are uploading a part from an existing object, you must be allowed s3:GetObject on the source object.
	Only the initiator of a multipart upload can upload parts. The bucket owner must allow the initiator to perform the $s3:PutObject$ action on an object in order for the initiator to upload a part for that object.
Complete Multipart	You must be allowed to perform the s3:PutObject action on an object to complete a multipart upload.
Upload	Only the initiator of a multipart upload can complete that multipart upload. The bucket owner must allow the initiator to perform the <code>s3:PutObject</code> action on an object in order for the initiator to complete a multipart upload for that object.
Abort Multipart Upload	You must be allowed to perform the s3: AbortMultipartUpload action to abort a multipart upload.
	By default, the bucket owner and the initiator of the multipart upload are allowed to perform this action. If the initiator is an IAM User, that User's AWS account is also allowed to abort that multipart upload.
	In addition to these defaults, the bucket owner can allow other principals to perform the s3:AbortMultipartUpload action on an object. The bucket owner can deny any principal the ability to perform the s3:AbortMultipartUpload action.
List Parts	You must be allowed to perform the s3:ListMultipartUploadParts action to list parts in a multipart upload.
	By default, the bucket owner has permission to list parts for any multipart upload to the bucket. The initiator of the multipart upload has the permission to list parts of the specific multipart upload. If the multipart upload initiator is an IAM User, the AWS account controlling that IAM User also has permission to list parts of that upload.
	In addition to these defaults, the bucket owner can allow other principals to perform the $s3:ListMultipartUploadParts$ action on an object. The bucket owner can also deny any principal the ability to perform the $s3:ListMultipartUploadParts$ action.
List Multipart Uploads	You must be allowed to perform the s3:ListBucketMultipartUploads action on a bucket to list multipart uploads in progress to that bucket.
	In addition to the default, the bucket owner can allow other principals to perform the s3:ListBucketMultipartUploads action on the bucket.

For additional information on actions and their use in policies, see Action (p. 344). For information on the relationship between policy actions and ACL permissions, see Relationship Between Actions and Permissions (p. 244). For information on IAM Users, go to Working with Users and Groups.

Getting Objects

Topics

- Related Resources (p. 110)
- Get an Object Using the AWS SDK for Java (p. 110)
- Get an Object Using the AWS SDK for .NET (p. 113)
- Get an Object Using the AWS SDK for PHP (p. 116)

Amazon Simple Storage Service Developer Guide Related Resources

- Get an Object Using REST API (p. 118)
- Share an Object with Others (p. 118)

You can retrieve objects directly from Amazon S3. You have the following options when retrieving an object:

- Retrieve an entire object—A single GET operation can return you the entire object stored in Amazon S3.
- Retrieve object in parts—Using the Range HTTP header in a GET request, you can retrieve a specific range of bytes in an object stored in Amazon S3.

You resume fetching other parts of the object whenever your application is ready. This resumable download is useful when you need only portions of your object data. It is also useful where network connectivity is poor and you need to react to failures.

When you retrieve an object, its metadata is returned in the response headers. There are times when you want to override certain response header values returned in a GET response. For example, you might override the Content-Disposition response header value in your GET request. The REST GET Object API (see GET Object) allows you to specify query string parameters in your GET request to override these values. The AWS SDK for Java, .NET and PHP also provide necessary objects you can use to specify values for these response headers in your GET request.

Related Resources

Using the AWS SDKs and Explorers (p. 325)

Get an Object Using the AWS SDK for Java

When you download an object, you get all of object's metadata and a stream from which to read the contents. You should read the content of the stream as quickly as possible because the data is streamed directly from Amazon S3 and your network connection will remain open until you read all the data or close the input stream.

Downloading Objects

1	Create an instance of the AmazonS3Client class by providing your AWS credentials.
2	Execute one of the AmazonS3Client.getObject() method. You need to provide the request information, such as bucket name, and key name. You provide this information by creating an instance of the GetObjectRequest class.
3	Execute one of the <code>getObjectContent()</code> methods on the object returned to get a stream on the object data and process the response.

The following Java code sample demonstrates the preceding tasks.

Amazon Simple Storage Service Developer Guide Get an Object Using the AWS SDK for Java

```
// Process the objectData stream.
objectData.close();
```

The GetObjectRequest object provides several options, including conditional downloading of objects based on modification times, ETags, and selectively downloading a range of an object. The following Java code sample demonstrates how you can specify a range of data bytes to retrieve from an object.

When retrieving an object, you can optionally override the response header values (see Getting Objects (p. 109)) by using the ResponseHeaderOverrides object and setting the corresponding request property, as shown in the following Java code sample.

```
GetObjectRequest request = new GetObjectRequest(bucketName, key);

ResponseHeaderOverrides responseHeaders = new ResponseHeaderOverrides();
responseHeaders.setCacheControl("No-cache");
responseHeaders.setContentDisposition("attachment; filename=testing.txt");

// Add the ResponseHeaderOverides to the request.
request.setResponseHeaders(responseHeaders);
```

The following Java code example retrieves an object from a specified Amazon S3 bucket. For instructions on how to create and test a working sample, see Testing the Java Code Examples (p. 327)

```
import java.io.BufferedReader;
import java.io.IOException;
import java.io.InputStream;
import java.io.InputStreamReader;
import com.amazonaws.AmazonClientException;
import com.amazonaws.AmazonServiceException;
import com.amazonaws.auth.PropertiesCredentials;
import com.amazonaws.services.s3.AmazonS3;
import com.amazonaws.services.s3.AmazonS3Client;
import com.amazonaws.services.s3.model.GetObjectRequest;
import com.amazonaws.services.s3.model.S3Object;
public class S3Sample {
private static String bucketName = "*** Provide bucket name ***";
                                 = "*** Provide Key ***";
private static String key
public static void main(String[] args) throws IOException {
       AmazonS3 s3Client = new AmazonS3Client(new PropertiesCredentials(
               S3Sample.class.getResourceAsStream(
                  "AwsCredentials.properties")));
        try {
           System.out.println("Downloading an object");
           S30bject s3object = s3Client.getObject(new GetObjectRequest(
             bucketName, key));
           System.out.println("Content-Type: " +
              s3object.getObjectMetadata().getContentType());
           displayTextInputStream(s3object.getObjectContent());
           // Get a range of bytes from an object.
           GetObjectRequest rangeObjectRequest = new GetObjectRequest(
             bucketName, key);
           rangeObjectRequest.setRange(0, 10);
           S3Object objectPortion = s3Client.getObject(rangeObjectRequest);
           System.out.println("Printing bytes retrieved.");
           displayTextInputStream(objectPortion.getObjectContent());
        } catch (AmazonServiceException ase) {
           System.out.println("Caught an AmazonServiceException, which" +
              " means your request made it " +
                    "to Amazon S3, but was rejected with an error response" +
                    " for some reason.");
           System.out.println("Error Message:
                                                  " + ase.getMessage());
           System.out.println("HTTP Status Code: " + ase.getStatusCode());
           System.out.println("AWS Error Code: " + ase.getErrorCode());
           System.out.println("Error Type:
                                                  " + ase.getErrorType());
                                                 " + ase.getRequestId());
           System.out.println("Request ID:
        } catch (AmazonClientException ace) {
           System.out.println("Caught an AmazonClientException, which means"+
              " the client encountered " +
```

Get an Object Using the AWS SDK for .NET

The following tasks guide you through using the .NET classes to retrieve an object or a portion of the object.

Downloading Objects

1	Create an instance of the AmazonS3 class by providing your AWS credentials.
2	Execute one of the AmazonS3.GetObject methods. You need to provide information such as buckname, file path, or a stream. You provide this information by creating an instance of the GetObjectRequest class.
3	Execute one of the GetObjectResponse.WriteResponseStreamToFile methods to save the stream to a file.

The following C# code sample demonstrates the preceding tasks.

Amazon Simple Storage Service Developer Guide Get an Object Using the AWS SDK for .NET

```
response.WriteResponseStreamToFile(dest);
}
```

Instead of reading the entire object you can read only the portion of the object data by specifying the byte range in the request, as shown in the following C# code sample.

```
GetObjectRequest request = new GetObjectRequest()
   .WithBucketName(bucketName)
   .WithKey(keyName)
   .WithByteRange(0, 10);
```

When retrieving an object, you can optionally override the response header values (see Getting Objects (p. 109)) by using the ResponseHeaderOverrides object and setting the corresponding request property, as shown in the following C# code sample.

```
GetObjectRequest request = new GetObjectRequest()
    .WithBucketName(bucketName).WithKey(keyName);

ResponseHeaderOverrides responseHeaders = new ResponseHeaderOverrides();
responseHeaders.CacheControl = "No-cache";
responseHeaders.ContentDisposition = "attachment; filename=testing.txt";
request.ResponseHeaderOverrides = responseHeaders;
```

The following C# code example retrieves an object from an Amazon S3 bucket. From the response, the example reads the object data using the GetObjectResponse.ResponseStream property. For instructions on how to create and test a working sample, see Testing the .NET Code Examples (p. 328)

```
using System;
using System.Configuration;
using System.Collections.Specialized;
using System.IO;
using Amazon.S3;
using Amazon.S3.Model;
namespace s3.amazon.com.docsamples.retrieveobject
    class S3Sample
        static string bucketName = "*** Provide bucket name ***";
                                 = "*** Provide object key ***";
        static string keyName
        static AmazonS3 client;
        public static void Main(string[] args)
            if (checkRequiredFields())
            {
                NameValueCollection appConfig =
                    ConfigurationManager.AppSettings;
                string accessKeyID = appConfig["AWSAccessKey"];
                string secretAccessKeyID = appConfig["AWSSecretKey"];
                try
                    Console.WriteLine("Retrieving (getting) an object");
                    string data = ReadingAnObject(
                                             accessKeyID, secretAccessKeyID);
                catch (AmazonS3Exception s3Exception)
                    Console.WriteLine(s3Exception.Message,
                                      s3Exception.InnerException);
                }
            Console.WriteLine("Press any key to continue...");
            Console.ReadKey();
        static string ReadingAnObject(
                       string accessKeyID, string secretAccessKeyID)
            string responseBody = "";
            using (client = Amazon.AWSClientFactory.CreateAmazonS3Client(
                                             accessKeyID, secretAccessKeyID))
                GetObjectRequest request = new GetObjectRequest()
                    .WithBucketName(bucketName).WithKey(keyName);
```

```
using (GetObjectResponse response = client.GetObject(request))
            {
                string title = response.Metadata["x-amz-meta-title"];
                Console.WriteLine("The object's title is {0}", title);
                using (Stream responseStream = response.ResponseStream)
                    using (StreamReader reader =
                        new StreamReader(responseStream))
                        responseBody = reader.ReadToEnd();
            }
        return responseBody;
   static bool checkRequiredFields()
        NameValueCollection appConfig = ConfigurationManager.AppSettings;
        if (string.IsNullOrEmpty(appConfig["AWSAccessKey"]))
            Console.WriteLine(
                "AWSAccessKey was not set in the App.config file.");
            return false;
        if (string.IsNullOrEmpty(appConfig["AWSSecretKey"]))
            Console.WriteLine(
                "AWSSecretKey was not set in the App.config file.");
            return false;
        if (string.IsNullOrEmpty(bucketName))
            Console.WriteLine("The variable bucketName is not set.");
            return false;
        if (string.IsNullOrEmpty(keyName))
            Console.WriteLine("The variable keyName is not set.");
            return false;
        return true;
}
```

Get an Object Using the AWS SDK for PHP

The following tasks guide you through using the PHP classes to retrieve an object. You can retrieve an entire object or only a specific byte range from the object.

Downloading Files

1	Create an instance of the AmazonS3 class by providing your AWS credentials.
2	Execute the AmazonS3::get_object() method. You need to provide a bucket name, and a key name as parameters.
	Instead of retrieving the entire object you can optionally retrieve a specific byte range from the object data. You provide the range value by specifying the optional array parameter with the range key.
	You can save the object you retrieved from Amazon S3, to a file in your local file system by specifying the optional array parameter with the fileDownload key.

The following PHP code sample demonstrates the preceding tasks.

When retrieving an object, you can optionally override the response header values (see Getting Objects (p. 109)) by adding the optional response parameter to the get_object method, as shown in the following PHP code sample.

The following PHP example retrieves an object and displays object content in the browser. The example illustrates the use of the <code>qet_object()</code> method.

Get an Object Using REST API

You can use AWS SDK to list object keys in a bucket. However, if your application requires it, you can send REST requests directly. You can send a GET request to retrieve object keys. For more information about the request and response format, go to Get Bucket (List Objects).

Share an Object with Others

Topics

- Generate Pre-signed Object URL using AWS Explorer for Visual Studio (p. 119)
- Generate Pre-signed Object URL using AWS SDK for Java (p. 119)
- Generate Pre-signed Object URL using AWS SDK for .NET (p. 121)

All objects by default are private. Only the object owner has permission to access these objects. However, the object owner can optionally share objects with others by creating a pre-signed URL, using their own security credentials, to grant time-limited permission to download the objects.

When you create a pre-signed URL for your object, you must provide your security credentials, specify a bucket name, an object key, specify the HTTP method (GET to download the object) and expiration date and time. The pre-signed URLs are valid only for the specified duration.

Anyone who recieves the pre-signed URL can then access the object. For example, if you have a video in your bucket and both the bucket and the object are private, you can share the video with others by generating a pre-signed URL.

Amazon Simple Storage Service Developer Guide Share an Object with Others



Note

Anyone with valid security credentials can create a pre-signed URL. However, in order to successfully access an object, the pre-signed URL must be created by someone who has permission to perform the operation that the pre-signed URL is based upon.

You can generate pre-signed URL programmatically using the AWS SDK for Java and .NET.

Generate Pre-signed Object URL using AWS Explorer for Visual Studio

If you are using Visual Studio, you can generate a pre-signed URL for an object without writing any code by using the AWS Explorer for Visual Studio. Anyone with this URL can download the object. For more information, go to Using Amazon S3 from AWS Explorer.

For instructions about how to install the AWS Explorer, see Using the AWS SDKs and Explorers (p. 325).

Generate Pre-signed Object URL using AWS SDK for Java

The following tasks guide you through using the Java classes to generate a pre-signed URL.

Downloading Objects

1	Create an instance of the AmazonS3 class by providing your AWS credentials. These credentials are used in creating a signature for authentication when you generate a pre-signed URL.	
2	Execute the AmazonS3.generatePresignedUrl method to generate a pre-signed URL. You provide information including a bucket name, an object key, and an expiration date by creating an instance of the GeneratePresignedUrlRequest class.	

The following Java code sample demonstrates the preceding tasks.

The following Java code example generates a pre-signed URL that you can give to others so that they can retrieve the object. For instructions about how to create and test a working sample, see Testing the Java Code Examples (p. 327)

```
import java.io.IOException;
import java.net.URL;
import com.amazonaws.AmazonClientException;
import com.amazonaws.AmazonServiceException;
import com.amazonaws.HttpMethod;
import com.amazonaws.auth.PropertiesCredentials;
import com.amazonaws.services.s3.AmazonS3;
import com.amazonaws.services.s3.AmazonS3Client;
import com.amazonaws.services.s3.model.GeneratePresignedUrlRequest;
import java.net.*;
import java.io.*;
public class S3Sample {
private static String bucketName = "*** Provide a bucket name ***";
private static String objectKey = "*** Provide an object key ***";
public static void main(String[] args) throws IOException {
 AmazonS3 s3client = new AmazonS3Client(new PropertiesCredentials(
  S3Sample.class.getResourceAsStream("AwsCredentials.properties")));
 try {
  System.out.println("Generating pre-signed URL.");
  java.util.Date expiration = new java.util.Date();
  long milliSeconds = expiration.getTime();
  milliSeconds += 1000 * 60 * 60; // Add 1 hour.
  expiration.setTime(milliSeconds);
  GeneratePresignedUrlRequest generatePresignedUrlRequest =
       new GeneratePresignedUrlRequest(bucketName, objectKey);
  generatePresignedUrlRequest.setMethod(HttpMethod.GET);
  generatePresignedUrlRequest.setExpiration(expiration);
  URL url = s3client.generatePresignedUrl(generatePresignedUrlRequest);
  System.out.println("Pre-Signed URL = " + url.toString());
 } catch (AmazonServiceException exception) {
  System.out.println("Caught an AmazonServiceException, " +
     "which means your request made it " +
     "to Amazon S3, but was rejected with an error response " +
   "for some reason.");
  System.out.println("Error Message: " + exception.getMessage());
  System.out.println("HTTP Code: " + exception.getStatusCode());
  System.out.println("AWS Error Code:" + exception.getErrorCode());
  System.out.println("Error Type: " + exception.getErrorType());
                                     " + exception.getRequestId());
  System.out.println("Request ID:
 } catch (AmazonClientException ace) {
  System.out.println("Caught an AmazonClientException, " +
     "which means the client encountered " +
     "an internal error while trying to communicate" +
     " with S3, " +
   "such as not being able to access the network.");
```

Amazon Simple Storage Service Developer Guide Share an Object with Others

```
System.out.println("Error Message: " + ace.getMessage());
}
}
```

Generate Pre-signed Object URL using AWS SDK for .NET

The following tasks guide you through using the .NET classes to generate a pre-signed URL.

Downloading Objects

1	Create an instance of the AmazonS3 class by providing your AWS credentials. These credentials are used in creating a signature for authentication when you generate a pre-signed URL.	
2	Execute the AmazonS3.GetPreSignedURL method to generate a pre-signed URL. You provide information including a bucket name, an object key, and an expiration date by creating an instance of the GetPreSignedUrlRequest class.	

The following C# code sample demonstrates the preceding tasks.

The following C# code example generates a pre-signed URL for a specific object. For instructions about how to create and test a working sample, see Testing the .NET Code Examples (p. 328)

```
using System;
using System.Configuration;
using System.Collections.Specialized;
using Amazon.S3;
using Amazon.S3.Model;
namespace s3.amazon.com.docsamples.presignedurl
   class S3Sample
       static string bucketName = "*** Provide a bucket name ***";
       static string objectKey = "*** Provide an object name ***";
       static AmazonS3 s3Client;
       public static void Main(string[] args)
            NameValueCollection appConfig = ConfigurationManager.AppSettings;
            string accessKeyID = appConfig["AWSAccessKey"];
            string secretAccessKeyID = appConfig["AWSSecretKey"];
              using (s3Client = Amazon.AWSClientFactory.CreateAmazonS3Client(
                    accessKeyID, secretAccessKeyID))
                {
                        GeneratePreSignedURL();
                }
            Console.WriteLine("Press any key to continue...");
            Console.ReadKey();
        }
       static void GeneratePreSignedURL()
            GetPreSignedUrlRequest request = new GetPreSignedUrlRequest();
            request.WithBucketName(bucketName);
            request.WithKey(objectKey);
            request.WithExpires(DateTime.Now.AddMinutes(5));
            try
            {
                string url = s3Client.GetPreSignedURL(request);
            catch (AmazonS3Exception amazonS3Exception)
                if (amazonS3Exception.ErrorCode != null &&
                    (amazonS3Exception.ErrorCode.Equals("InvalidAccessKeyId")
                    amazonS3Exception.ErrorCode.Equals("InvalidSecurity")))
                    Console.WriteLine("Check the provided AWS Credentials.");
                    Console.WriteLine(
                    "To sign up for service, go to http://aws.amazon.com/s3");
```

Uploading Objects

Topics

- Related Resources (p. 123)
- Uploading Objects in a Single Operation (p. 123)
- Uploading Objects Using Multipart Upload API (p. 134)
- Uploading Objects Using Pre-Signed URLs (p. 168)

Depending on the size of the data you are uploading, Amazon S3 offers the following options:

• **Upload objects in a single operation**—With a single PUT operation you can upload objects up to 5 GB in size.

For more information, see Uploading Objects in a Single Operation (p. 123).

• Upload objects in parts—Using the Multipart upload API you can upload large objects, up to 5 TB. The Multipart Upload API is designed to improve the upload experience for larger objects. You can upload objects in parts. These object parts can be uploaded independently, in any order, and in parallel. You can use a Multipart Upload for objects from 5 MB to 5 TB in size. For more information, see Uploading Objects Using Multipart Upload. For more information, see Uploading Objects Using Multipart Upload API (p. 134).

We encourage Amazon S3 customers to use Multipart Upload for objects greater than 100 MB.

Related Resources

• Using the AWS SDKs and Explorers (p. 325)

Uploading Objects in a Single Operation

Topics

Upload an Object Using the AWS SDK for Java (p. 124)

Amazon Simple Storage Service Developer Guide Uploading Objects in a Single Operation

- Upload an Object Using the AWS SDK for .NET (p. 125)
- Upload an Object Using the AWS SDK for PHP (p. 129)
- Upload an Object Using the AWS SDK for Ruby (p. 132)
- Upload an Object Using the REST API (p. 133)

You can use the AWS SDK to upload objects. The SDK provides wrapper libraries for you to upload data easily. However, if your application requires it, you can use the REST API directly in your application.

Upload an Object Using the AWS SDK for Java

The following tasks guide you through using the Java classes to upload a file. The API provides several variations, called *overloads*, of the putObject method to easily upload your data.

Uploading Objects

1	Create an instance of the AmazonS3Client class by providing your AWS credentials.
2	Execute one of the AmazonS3Client.putObject overloads depending on whether you are uploading data from a file, or a stream.

The following Java code sample demonstrates the preceding tasks.

The following Java code example uploads a file to an Amazon S3 bucket. For instructions on how to create and test a working sample, see Testing the Java Code Examples (p. 327)

```
import java.io.File;
import java.io.IOException;
import com.amazonaws.AmazonClientException;
import com.amazonaws.AmazonServiceException;
import com.amazonaws.auth.PropertiesCredentials;
import com.amazonaws.services.s3.AmazonS3;
import com.amazonaws.services.s3.AmazonS3Client;
import com.amazonaws.services.s3.model.PutObjectRequest;
public class S3Sample {
private static String bucketName
                                    = "*** Provide bucket name ***";
                                     = "*** Provide key ***";
private static String keyName
private static String uploadFileName = "*** Provide file name ***";
public static void main(String[] args) throws IOException {
       AmazonS3 s3client = new AmazonS3Client(new PropertiesCredentials(
               S3Sample.class.getResourceAsStream(
                  "AwsCredentials.properties")));
        try {
            System.out.println("Uploading a new object to S3 from a file\n");
            File file = new File(uploadFileName);
            s3client.putObject(new PutObjectRequest(
                               bucketName, keyName, file));
         } catch (AmazonServiceException ase) {
            System.out.println("Caught an AmazonServiceException, which " +
              "means your request made it " +
                   "to Amazon S3, but was rejected with an error response" +
                    " for some reason.");
            System.out.println("Error Message:
                                                  " + ase.getMessage());
            System.out.println("HTTP Status Code: " + ase.getStatusCode());
            System.out.println("AWS Error Code: " + ase.getErrorCode());
            System.out.println("Error Type:
                                               " + ase.getErrorType());
            System.out.println("Request ID:
                                                  " + ase.getRequestId());
        } catch (AmazonClientException ace) {
            System.out.println("Caught an AmazonClientException, which " +
              "means the client encountered " +
                    "an internal error while trying to " +
                    "communicate with S3, " +
                    "such as not being able to access the network.");
            System.out.println("Error Message: " + ace.getMessage());
    }
}
```

Upload an Object Using the AWS SDK for .NET

The tasks in the following process guide you through using the .NET classes to upload an object. The API provides several variations, overloads, of the PutObject method to easily upload your data.

Amazon Simple Storage Service Developer Guide Uploading Objects in a Single Operation

Uploading Objects

1	Create an instance of the AmazonS3 class by providing your AWS credentials.
2	Execute one of the AmazonS3.PutObject. You need to provide information such as a bucket name, file path, or a stream. You provide this information by creating an instance of the PutObjectRequest class.

The following C# code sample demonstrates the preceding tasks.



Note

When uploading large objects using the .NET API, timeout might occur even while data is being written to the request stream. You can set explicit timeout using the PutObjectRequest object.

The following C# code example uploads an object. The object data is provided as a text string in the code. The example illustrates the use of the AmazonS3.PutObject to upload an object. The example uploads the object twice. In the first object upload, the PutObjectRequest specifies only the bucket name, key name, and sample object data. In the second object upload the PutObjectRequest provides additional information including the optional object metadata and a content type header. Each successive call to AmazonS3.PutObject replaces the previous upload. For instructions on how to create and test a working sample, see Testing the .NET Code Examples (p. 328)

```
using System;
using System.Configuration;
using System.Collections.Specialized;
using System.Net;
using Amazon.S3;
using Amazon.S3.Model;
using Amazon.S3.Util;
namespace s3.amazon.com.docsamples.createobject
   class S3Sample
        static string bucketName = "*** Provide bucket name ***";
                               = "*** Provide key name ***";
        static string keyName
        static AmazonS3 client;
        public static void Main(string[] args)
            if (checkRequiredFields())
                NameValueCollection appConfig =
                    ConfigurationManager.AppSettings;
                string accessKeyID = appConfig["AWSAccessKey"];
                string secretAccessKeyID = appConfig["AWSSecretKey"];
                using (client = Amazon.AWSClientFactory.CreateAmazonS3Client(
                    accessKeyID, secretAccessKeyID))
                    Console.WriteLine("Uploading an object");
                    WritingAnObject();
                 }
            }
            Console.WriteLine("Press any key to continue...");
            Console.ReadKey();
         static void WritingAnObject()
            try
                // 1. Simple object put.
                PutObjectRequest request = new PutObjectRequest();
                request.WithContentBody("Object data for simple put.")
```

```
.WithBucketName(bucketName)
           .WithKey(keyName);
       S3Response response = client.PutObject(request);
       response.Dispose();
      // 2. Put a more complex object with metadata and http headers.
       PutObjectRequest request2 = new PutObjectRequest();
       request2.WithMetaData("title", "the title")
           .WithContentBody("Object data for complex put.")
           //.WithFilePath(filePath)
           .WithBucketName(bucketName)
           .WithKey(keyName);
       // Add a header to the request.
       request2.AddHeaders(AmazonS3Util.CreateHeaderEntry
                                   ("ContentType", "text/xml"));
    S3Response responseWithMetadata = client.PutObject(request2);
   catch (AmazonS3Exception amazonS3Exception)
       if (amazonS3Exception.ErrorCode != null &&
           (amazonS3Exception.ErrorCode.Equals("InvalidAccessKeyId")
           amazonS3Exception.ErrorCode.Equals("InvalidSecurity")))
       {
           Console.WriteLine("Check the provided AWS Credentials.");
           Console.WriteLine(
               "For service sign up go to http://aws.amazon.com/s3");
       }
       else
           Console.WriteLine(
               "Error occurred. Message: '{0}' when writing an object"
               , amazonS3Exception.Message);
   }
static bool checkRequiredFields()
   NameValueCollection appConfig = ConfigurationManager.AppSettings;
    if (string.IsNullOrEmpty(appConfig["AWSAccessKey"]))
        Console.WriteLine(
            "AWSAccessKey was not set in the App.config file.");
        return false;
    if (string.IsNullOrEmpty(appConfig["AWSSecretKey"]))
        Console.WriteLine(
            "AWSSecretKey was not set in the App.config file.");
        return false;
```

Upload an Object Using the AWS SDK for PHP

The following tasks guide you through PHP classes to upload an object of up to 5 GB in size. For larger files you must use multipart upload API. For more information, see Uploading Objects Using Multipart Upload API (p. 134).

Uploading Objects

1	Create an instance of the AmazonS3 class by providing your AWS credentials.
2	Execute the AmazonS3::create_object() method. You need to provide information such as a bucket name, and key name. If you are uploading a file, you specify the file name by adding the array parameter with the fileUpload key. You can also provide the optional object metadata using the array parameter.

The following PHP code sample demonstrates the preceding tasks. The code sample creates an object by uploading a file specified in the fileUpload key in the array parameter.

```
// Instantiate the class.
$s3 = new AmazonS3();
$response = $s3->create_object(
    $bucket,
    $keyname2,
    array(
       'fileUpload' => $filePath,
       'acl' => AmazonS3::ACL_PUBLIC,
       'contentType' => 'text/plain',
       'storage' => AmazonS3::STORAGE_REDUCED,
'headers' => array( // raw headers
                           'Cache-Control' => 'max-age',
                           'Content-Encoding' => 'gzip',
                           'Content-Language' => 'en-US',
                           'Expires' => 'Thu, 01 Dec 1994 16:00:00 GMT',
          ),
         'meta'
                     => array(
```

Amazon Simple Storage Service Developer Guide Uploading Objects in a Single Operation

Instead of specifying a file name, you can provide object data inline by specifying the array parameter with the body key, as shown in the following PHP code example.

The following PHP example creates two objects in a specified bucket. The example creates an object first by uploading a file and then another object using the text string provided in the code. The example illustrates the use of the <code>create_object()</code> method to upload a file.

```
<?php
require_once '../aws-sdk-for-php/sdk.class.php';
$bucket = '*** Provide bucket name ***';
$keyname1 = '*** Provide object key ***';
$filepath = '*** Provide file name to upload ***';
$keyname2 = '*** Provide another object key ***';
// Instantiate the class
$s3 = new AmazonS3();
// 1. Create object from a file.
$response = $s3->create_object(
    $bucket,
    $keyname1,
    array('fileUpload' => $filepath)
    );
// Success?
print_r($response->isOK());
if ($response->isOK())
{
    echo "First upload successful!";
}
// 2. Create object from a string.
$response = $s3->create_object(
    $bucket,
    $keyname2,
    array(
       'body'
                    => 'This is object content',
       'acl'
                   => AmazonS3::ACL_PUBLIC,
       'contentType' => 'text/plain',
       'storage' => AmazonS3::STORAGE_REDUCED,
       'headers'
                     => array( // raw headers
                          'Cache-Control' => 'max-age',
                          'Content-Encoding' => 'gzip',
                          'Content-Language' => 'en-US',
                          'Expires' => 'Thu, 01 Dec 2010 16:00:00 GMT',
          ),
       'meta'
                  => array(
                          'param1' => 'value 1',
                          'param2' => 'value 2'
          )
    )
    );
// Success?
print_r($response->isOK());
if ($response->isOK())
```

Amazon Simple Storage Service Developer Guide Uploading Objects in a Single Operation

```
echo "Second upload successful!";
}
else
{
    print_r($response);
}
```

Upload an Object Using the AWS SDK for Ruby

The following tasks guide you through using the Ruby classes to upload a file. The API provides provides a #write method that can take options that you can use to specify how to upload your data.

Uploading Objects

1	Create an instance of the AWS::S3 class by providing your AWS credentials.
2	Use the AWS::S3::S3Object#write method which takes a data parameter and options hash which allow you to upload data from a file, or a stream.

The following Ruby code sample demonstrates the preceding tasks and uses the <code>options</code> hash <code>:file</code> to specify the path to the file to upload.

```
s3 = AWS::S3.new

# Upload a file.
key = File.basename(file_name)
s3.buckets[bucket_name].objects[key].write(:file => file_name)
```

Example

The following Ruby script example uploads a file to an Amazon S3 bucket. For instructions about how to create and test a working sample, see Using the AWS SDK for Ruby (p. 329).

```
#!/usr/bin/env ruby
require 'rubygems'
require 'aws-sdk'

AWS.config(
    :access_key_id => '*** Provide your access key ***',
    :secret_access_key => '*** Provide your secret key ***'
)

bucket_name = '*** Provide bucket name ***'
file_name = '*** Provide file name ****'

# Get an instance of the S3 interface.
s3 = AWS::S3.new

# Upload a file.
key = File.basename(file_name)
s3.buckets[bucket_name].objects[key].write(:file => file_name)
puts "Uploading file #{file_name} to bucket #{bucket_name}."
```

Upload an Object Using the REST API

You can use AWS SDK to upload an object. However, if your application requires it, you can send REST requests directly. You can send a PUT request to upload data in a single operation. For more information, go to PUT Object.

Uploading Objects Using Multipart Upload API

Topics

- Using the AWS SDK for Java for Multipart Upload (p. 135)
- Using the AWS SDK for .NET for Multipart Upload (p. 145)
- Using the AWS SDK for PHP for Multipart Upload (p. 161)
- Using the REST API for Multipart Upload (p. 167)

Multipart upload allows you to upload a single object as a set of parts. Each part is a contiguous portion of the object's data. You can upload these object parts independently and in any order. If transmission of any part fails, you can retransmit that part without affecting other parts. After all parts of your object are uploaded, Amazon S3 assembles these parts and creates the object. In general, when your object size reaches 100 MB, you should consider using multipart uploads instead of uploading the object in a single operation.

Using multipart upload provides the following advantages:

- Improved throughput—You can upload parts in parallel to improve throughput.
- Quick recovery from any network issues—Smaller part size minimizes the impact of restarting a failed upload due to a network error.
- Pause and resume object uploads—You can upload object parts over time. Once you initiate a multipart upload there is no expiry; you must explicitly complete or abort the multipart upload.
- Begin an upload before you know the final object size—You can upload an object as you are creating it.

Using the AWS SDK for Java for Multipart Upload

Topics

- Using the High-Level Java API for Multipart Upload (p. 135)
- Using the Low-Level Java API for Multipart Upload (p. 140)

As described in Using the AWS SDK (see Using the AWS SDKs and Explorers (p. 325)), the SDK for Java provides support for the multipart upload API (see Uploading Objects Using Multipart Upload API (p. 134)). This section provides examples of using the both high-level and the low-level Java SDK API for uploading objects in parts.

Using the High-Level Java API for Multipart Upload

Topics

- Upload a File (p. 135)
- Abort Multipart Uploads (p. 136)
- Track Multipart Upload Progress (p. 137)

The AWS SDK for Java exposes a high-level API that simplifies multipart upload (see Uploading Objects Using Multipart Upload API (p. 134)). You can upload data from a file or a stream. You can optionally set advanced options, such as the part size you want to use for the multipart upload, or the number of threads you want to use when uploading the parts concurrently. You can also set optional object properties, the storage class, or ACL. You use the PutObjectRequest and the TransferManagerConfiguration classes to set these advanced options. The TransferManager class of the Java API provides the high-level API for you to upload data.

In addition to file upload functionality, the TransferManager class provides a method for you to abort multipart upload in progress. You must provide a Date value, and then the API aborts all the multipart uploads that were initiated before the specified date.

Upload a File

The following tasks guide you through using the high-level Java classes to upload a file. The API provides several variations, called *overloads*, of the upload method to easily upload your data.

High-Level API File Uploading Process

1	Create an instance of the TransferManager class by providing your AWS credentials.
2	Execute one of the TransferManager.upload overloads depending on whether you are uploading data from a file, or a stream.

The following Java code sample demonstrates the preceding tasks.

```
AWSCredentials myCredentials = new BasicAWSCredentials(myAccessKeyID, mySecretKey);

TransferManager tm = new TransferManager(myCredentials);

// Asynchronous call.

Upload upload = tm.upload(existingBucketName, keyName, new File(filePath));
```

The following Java code example uploads a file to an Amazon S3 bucket. For instructions on how to create and test a working sample, see Testing the Java Code Examples (p. 327)

```
import java.io.File;
import com.amazonaws.AmazonClientException;
import com.amazonaws.auth.PropertiesCredentials;
import com.amazonaws.services.s3.transfer.TransferManager;
import com.amazonaws.services.s3.transfer.Upload;
public class HighLevel_Java_UploadFile {
    public static void main(String[] args) throws Exception {
        String existingBucketName = "*** Provide existing bucket name ***";
        String keyName
                          = "*** Provide object key ***";
                                = "*** Provide file to upload ***";
       String filePath
        TransferManager tm = new TransferManager(new PropertiesCredentials(
         HighLevel_Java_UploadFile.class.getResourceAsStream(
                               "AwsCredentials.properties")));
        // TransferManager processes all transfers asynchronously,
        // so this call will return immediately.
        Upload upload = tm.upload(
          existingBucketName, keyName, new File(filePath));
        try {
         // Or you can block and wait for the upload to finish
        upload.waitForCompletion();
        } catch (AmazonClientException amazonClientException) {
        System.out.println("Unable to upload file, upload was aborted.");
        amazonClientException.printStackTrace();
    }
}
```

Abort Multipart Uploads

The TransferManager class provides a method, abortMultipartUploads, to abort multipart uploads in progress. An upload is considered to be in progress once you initiate it and until you complete it or abort it. You provide a Date value and this API aborts all the multipart uploads, on that bucket, that were initiated before the specified Date and are still in progress.

Because you are billed for all storage associated with uploaded parts (see Multipart Upload and Pricing (p. 107)), it is important that you either complete the multipart upload to have the object created or abort the multipart upload to remove any uploaded parts.

The following tasks guide you through using the high-level Java classes to abort multipart uploads.

High-Level API Multipart Uploads Aborting Process

1	Create an instance of the TransferManager class by providing your AWS credentials.
2	Execute the TransferManager.abortMultipartUploads method by passing the bucket name and a Date value.

The following Java code sample demonstrates the preceding tasks.

```
AWSCredentials myCredentials = new BasicAWSCredentials(myAccessKeyID,
mySecretKey);

TransferManager tm = new TransferManager(myCredentials);
tm.abortMultipartUploads(existingBucketName, someDate);
```

Example

The following Java code aborts all multipart uploads in progress that were initiated on a specific bucket over a week ago. For instructions on how to create and test a working sample, see Testing the Java Code Examples (p. 327)

```
import java.util.Date;
import com.amazonaws.AmazonClientException;
import com.amazonaws.auth.PropertiesCredentials;
import com.amazonaws.services.s3.transfer.TransferManager;
public class HighLevel_Java_AbortMultipartUploads {
   public static void main(String[] args) throws Exception {
        String existingBucketName = "*** Provide existing bucket name ***";
        TransferManager tm = new TransferManager(new PropertiesCredentials(
          HighLevel_Java_UploadFile.class.getResourceAsStream(
                           "AwsCredentials.properties")));
        int sevenDays = 1000 * 60 * 60 * 24 * 7;
 Date oneWeekAgo = new Date(System.currentTimeMillis() - sevenDays);
        try {
        tm.abortMultipartUploads(existingBucketName, oneWeekAgo);
        } catch (AmazonClientException amazonClientException) {
         System.out.println("Unable to upload file, upload was aborted.");
         amazonClientException.printStackTrace();
    }
```



Note

You can also abort a specific multipart upload. For more information, see Abort a Multipart Upload (p. 144).

Track Multipart Upload Progress

The high-level multipart upload API provides a listen interface, ProgressListener, to track the upload progress when uploading data using the TransferManager class. To use the event in your code, you must import the com.amazonaws.services.s3.model.ProgressEvent and com.amazonaws.services.s3.model.ProgressListener types.

Progress events occurs periodically and notify the listener that bytes have been transferred.

The following Java code sample demonstrates how you can subscribe to the ProgressEvent event and write a handler.

The following Java code uploads a file and uses the ProgressListener to track the upload progress. For instructions on how to create and test a working sample, see Testing the Java Code Examples (p. 327)

```
import java.io.File;
import com.amazonaws.AmazonClientException;
import com.amazonaws.auth.PropertiesCredentials;
import com.amazonaws.services.s3.model.ProgressEvent;
import com.amazonaws.services.s3.model.ProgressListener;
import com.amazonaws.services.s3.model.PutObjectRequest;
import com.amazonaws.services.s3.transfer.TransferManager;
import com.amazonaws.services.s3.transfer.Upload;
public class HighLevel_Java_UploadFile {
    public static void main(String[] args) throws Exception {
       String existingBucketName = "*** Provide bucket name ***";
                                 = "*** Provide object key ***";
        String keyName
        String filePath
                                 = "** Provide file to upload ***";
        TransferManager tm = new TransferManager(new PropertiesCredentials(
        HighLevel_Java_UploadFile.class.getResourceAsStream(
                                 "AwsCredentials.properties")));
        // For more advanced uploads, you can create a request object
        // and supply additional request parameters (ex: progress listeners,
        // canned ACLs, etc)
        PutObjectRequest request = new PutObjectRequest(
          existingBucketName, keyName, new File(filePath));
        // You can ask the upload for its progress, or you can
        // add a ProgressListener to your request to receive notifications
        // when bytes are transfered.
        request.setProgressListener(new ProgressListener() {
  public void progressChanged(ProgressEvent event) {
    System.out.println("Transferred bytes: " +
      event.getBytesTransfered());
  });
        // TransferManager processes all transfers asynchronously,
        // so this call will return immediately.
        Upload upload = tm.upload(request);
        try {
        // You can block and wait for the upload to finish
        upload.waitForCompletion();
        } catch (AmazonClientException amazonClientException) {
         System.out.println("Unable to upload file, upload aborted.");
        amazonClientException.printStackTrace();
    }
```

Using the Low-Level Java API for Multipart Upload

Topics

- Upload a File (p. 140)
- List Multipart Uploads (p. 143)
- Abort a Multipart Upload (p. 144)

The AWS SDK for Java exposes a low-level API that closely resembles to the Amazon S3 REST API for multipart upload (see Uploading Objects Using Multipart Upload API (p. 134).

Upload a File

The following tasks guide you through using the low-level Java classes to upload a file.

Low-Level API File Uploading Process

1	Create an instance of the AmazonS3Client class, by providing your AWS credentials.
2	Initiate multipart upload by executing the AmazonS3Client.initiateMultipartUpload method. You will need to provide information required, i.e., bucket name and key name, to initiate the multipart upload by creating an instance of the InitiateMultipartUploadRequest class.
3	Save the upload ID that the AmazonS3Client.initiateMultipartUpload method returns. You will need to provide this upload ID for each subsequent multipart upload operation.
4	Upload parts. For each part upload, execute the AmazonS3Client.uploadPart method. You need to provide part upload information, such as upload ID, bucket name, and the part number. You provide this information by creating an instance of the UploadPartRequest class.
5	Save the response of the AmazonS3Client.uploadPart method in a list. This response includes the ETag value and the part number you will need to complete the multipart upload.
6	Repeat tasks 4 and 5 for each part.
7	Execute the AmazonS3Client.completeMultipartUpload method to complete the multipart upload.

The following Java code sample demonstrates the preceding tasks.

```
s3Client.initiateMultipartUpload(initRequest);
File file = new File(filePath);
long contentLength = file.length();
long partSize = 5 * 1024 * 1024; // Set part size to 5 MB.
try {
    // Step 2: Upload parts.
    long filePosition = 0;
    for (int i = 1; filePosition < contentLength; i++) {</pre>
        // Last part can be less than 5 MB. Adjust part size.
    partSize = Math.min(partSize, (contentLength - filePosition));
        // Create request to upload a part.
        UploadPartRequest uploadRequest = new UploadPartRequest()
            .withBucketName(existingBucketName).withKey(keyName)
            .withUploadId(initResponse.getUploadId()).withPartNumber(i)
            .withFileOffset(filePosition)
            .withFile(file)
            .withPartSize(partSize);
        // Upload part and add response to our list.
        partETags.add(s3Client.uploadPart(uploadRequest).getPartETag());
        filePosition += partSize;
    }
    // Step 3: complete.
    CompleteMultipartUploadRequest compRequest = new
                CompleteMultipartUploadRequest(existingBucketName,
                                                keyName,
                                                initResponse.getUploadId(),
                                                partETags);
    s3Client.completeMultipartUpload(compRequest);
} catch (Exception e) {
    s3Client.abortMultipartUpload(new AbortMultipartUploadRequest(
              existingBucketName, keyName, initResponse.getUploadId()));
```

The following Java code example uploads a file to an Amazon S3 bucket. For instructions on how to create and test a working sample, see Testing the Java Code Examples (p. 327).

```
import java.io.File;
import java.io.IOException;
import java.util.ArrayList;
import java.util.List;
import com.amazonaws.auth.PropertiesCredentials;
import com.amazonaws.services.s3.AmazonS3;
import com.amazonaws.services.s3.AmazonS3Client;
import com.amazonaws.services.s3.model.AbortMultipartUploadRequest;
import com.amazonaws.services.s3.model.CompleteMultipartUploadRequest;
import com.amazonaws.services.s3.model.InitiateMultipartUploadRequest;
import com.amazonaws.services.s3.model.InitiateMultipartUploadResult;
import com.amazonaws.services.s3.model.ListMultipartUploadsRequest;
import com.amazonaws.services.s3.model.ListPartsRequest;
import com.amazonaws.services.s3.model.MultipartUploadListing;
import com.amazonaws.services.s3.model.PartETag;
import com.amazonaws.services.s3.model.PartListing;
import com.amazonaws.services.s3.model.UploadPartRequest;
public class LowLevel_Java_UploadFile {
   public static void main(String[] args) throws IOException {
       String existingBucketName="*** Provide-Your-Existing-BucketName ***";
                                   = "*** Provide-Key-Name ***";
       String keyName
       String filePath
                                   = "*** Provide-File-Path ***";
       AmazonS3 s3Client = new AmazonS3Client(new PropertiesCredentials(
         LowLevel_Java_UploadFile.class.getResourceAsStream(
                              "AwsCredentials.properties")));
        // Create a list of UploadPartResponse objects. You get one of these
        // for each part upload.
       List<PartETag> partETags = new ArrayList<PartETag>();
        // Step 1: Initialize.
        InitiateMultipartUploadRequest initRequest = new
             InitiateMultipartUploadRequest(existingBucketName, keyName);
        InitiateMultipartUploadResult initResponse =
                            s3Client.initiateMultipartUpload(initRequest);
        File file = new File(filePath);
        long contentLength = file.length();
        long partSize = 5242880; // Set part size to 5 MB.
        try {
            // Step 2: Upload parts.
            long filePosition = 0;
            for (int i = 1; filePosition < contentLength; i++) {</pre>
                // Last part can be less than 5 MB. Adjust part size.
            partSize = Math.min(partSize, (contentLength - filePosition));
                // Create request to upload a part.
```

```
UploadPartRequest uploadRequest = new UploadPartRequest()
                    .withBucketName(existingBucketName).withKey(keyName)
                   .withUploadId(initResponse.getUploadId()).withPartNumber(i)
                    .withFileOffset(filePosition)
                    .withFile(file)
                    .withPartSize(partSize);
                // Upload part and add response to our list.
                partETags.add(
                  s3Client.uploadPart(uploadRequest).getPartETag());
                filePosition += partSize;
            }
            // Step 3: complete.
            CompleteMultipartUploadRequest compRequest = new
                         CompleteMultipartUploadRequest(
                                    existingBucketName,
                                    keyName,
                                    initResponse.getUploadId(),
                                    partETags);
            s3Client.completeMultipartUpload(compRequest);
        } catch (Exception e) {
            s3Client.abortMultipartUpload(new AbortMultipartUploadRequest(
                    existingBucketName, keyName, initResponse.getUploadId()));
   }
}
```

List Multipart Uploads

The following tasks guide you through using the low-level Java classes to list all in-progress multipart uploads on a bucket.

Low-Level API Multipart Uploads Listing Process

1	Create an instance of the ListMultipartUploadsRequest class and provide the bucket name.	
2	Execute the AmazonS3Client.listMultipartUploads method. The method returns an instance of the MultipartUploadListing class that gives you information about the multipart uploads in progress.	

The following Java code sample demonstrates the preceding tasks.

```
ListMultipartUploadsRequest allMultpartUploadsRequest =
new ListMultipartUploadsRequest(existingBucketName);
MultipartUploadListing multipartUploadListing =
s3Client.listMultipartUploads(allMultpartUploadsRequest);
```

Abort a Multipart Upload

You can abort an in-progress multipart upload by calling the AmazonS3.abortMultipartUpload method. This method deletes any parts that were uploaded to Amazon S3 and frees up the resources. You must provide the upload ID, bucket name, and the key name. The following Java code sample demonstrates how you can abort a multipart upload in progress.



Note

Instead of a specific multipart upload, you can abort all your multipart uploads initiated before a specific time that are still in progress. This clean-up operation is useful to abort old multipart uploads that you initiated but neither completed or aborted. For more information, see Abort Multipart Uploads (p. 136).

Using the AWS SDK for .NET for Multipart Upload

Topics

- Using the High-Level .NET API for Multipart Upload (p. 145)
- Using the Low-Level .NET API for Multipart Upload (p. 155)

As described in Using the AWS SDK (see Using the AWS SDKs and Explorers (p. 325)), the SDK for .NET provides support for the multipart upload API (see Uploading Objects Using Multipart Upload API (p. 134)). This section provides examples of using the high-level and the low-level Java SDK API for uploading objects in parts.

Using the High-Level .NET API for Multipart Upload

Topics

- Upload a File (p. 145)
- Upload a Directory (p. 148)
- Abort Multipart Uploads (p. 151)
- Track Multipart Upload Progress (p. 152)

The AWS SDK for .NET exposes a high-level API that simplifies multipart upload (see Uploading Objects Using Multipart Upload API (p. 134)). You can upload data from a file, directory, or a stream. When uploading data from a file, if you don't provide the object's key name, the API uses the file name for the object's key name. You must provide the object's key name if you are uploading data from a stream. You can optionally set advanced options such as the part size you want to use for the multipart upload, number of threads you want to use when uploading the parts concurrently, optional file metadata, the storage class (STANDARD or REDUCED_REDUNDANCY), or ACL. The high-level API provides the TransferUtilityUploadRequest class to set these advanced options.

The TransferUtility class provides a method for you to abort multipart uploads in progress. You must provide a DateTime value, and then the API aborts all the multipart uploads that were initiated before the specified date and time.

Upload a File

The following tasks guide you through using the high-level .NET classes to upload a file. The API provides several variations, *overloads*, of the <code>Upload</code> method to easily upload your data.

High-Level API File Uploading Process

1	Create an instance of the TransferUtility class by providing your AWS credentials.
2	Execute one of the TransferUtility. Upload overloads depending on whether you are uploading data from a file, a stream, or a directory.

The following C# code sample demonstrates the preceding tasks.

```
TransferUtility utility = new TransferUtility(accessKeyID, secretAccessKey);
utility.Upload(filePath, existingBucketName);
```

When uploading large files using the .NET API, timeout might occur even while data is being written to the request stream. You can set explicit timeout using the TransferUtilityConfig.DefaultTimeout as demonstrated in the following C# code sample.

```
TransferUtilityConfig config = new TransferUtilityConfig();
config.DefaultTimeout = 11111;
TransferUtility utility = new TransferUtility(accessKeyID, secretAccessKey, config);
```

The following C# code example uploads a file to an Amazon S3 bucket. The example illustrates the use of various TransferUtility.Upload overloads to upload a file; each successive call to upload replaces the previous upload. For instructions on how to create and test a working sample, see Testing the .NET Code Examples (p. 328)

```
using System;
using System.Configuration;
using Amazon.S3;
using Amazon.S3.Model;
using System.Collections.Specialized;
using Amazon.S3.Transfer;
using System.IO;
namespace s3.amazon.com.docsamples.highlevel_uploadfile
   class Program
       static string accessKeyID
       static string secretAccessKey = "";
        static string existingBucketName = "*** Provide bucket name ***";
        static string keyName = "*** Provide your object key ***";
       static string filePath
                                    = "*** Provide file name ***";
       static void Main(string[] args)
            NameValueCollection appConfig = ConfigurationManager.AppSettings;
            accessKeyID = appConfig["AWSAccessKey"];
            secretAccessKey = appConfig["AWSSecretKey"];
            try
            {
                TransferUtility fileTransferUtility = new
                    TransferUtility(accessKeyID, secretAccessKey);
                // 1. Upload a file, file name is used as the object key name.
                fileTransferUtility.Upload(filePath, existingBucketName);
                Console.WriteLine("Upload 1 completed");
                // 2. Specify object key name explicitly.
                fileTransferUtility.Upload(filePath,
                                          existingBucketName, keyName);
                Console.WriteLine("Upload 2 completed");
                // 3. Upload data from a type of System.IO.Stream.
                using (FileStream fileToUpload =
                    new FileStream(filePath, FileMode.Open, FileAccess.Read))
                    fileTransferUtility.Upload(fileToUpload,
                                               existingBucketName, keyName);
                Console.WriteLine("Upload 3 completed");
                // 4.// Specify advanced settings/options.
```

```
TransferUtilityUploadRequest fileTransferUtilityRequest =
                    new TransferUtilityUploadRequest()
                    .WithBucketName(existingBucketName)
                    .WithFilePath(filePath)
                    .WithStorageClass(S3StorageClass.ReducedRedundancy)
                    .WithMetadata("param1", "Value1")
                    .WithMetadata("param2", "Value2")
                    .WithPartSize(6291456) // This is 6 MB.
                    .WithKey(keyName)
                    .WithCannedACL(S3CannedACL.PublicRead);
                fileTransferUtility.Upload(fileTransferUtilityRequest);
                Console.WriteLine("Upload 4 completed");
            }
            catch (AmazonS3Exception s3Exception)
                Console.WriteLine(s3Exception.Message,
                                  s3Exception.InnerException);
            }
        }
    }
}
```

Upload a Directory

Using the TransferUtility class you can also upload an entire directory. By default, Amazon S3 only uploads the files at the root of the specified directory. You can, however, specify to recursively upload files in all the subdirectories.

You can also specify filtering expressions to select files, in the specified directory, based on some filtering criteria. For example, to upload only the .pdf files from a directory you specify a "*.pdf" filter expression.

When uploading files from a directory you cannot specify the object's key name. It is constructed from the file's location in the directory as well as its name. For example, assume you have a directory, c:\myfolder, with the following structure:

When you upload this directory, Amazon S3 uses the following key names:

```
a.txt
b.pdf
media/An.mp3
```

The following tasks guide you through using the high-level .NET classes to upload a directory.

High-Level API Directory Uploading Process

1	Create an instance of the TransferUtility class by providing your AWS credentials.	
2	Execute one of the TransferUtility. UploadDirectory overloads.	

The following C# code sample demonstrates the preceding tasks.

TransferUtility utility = new TransferUtility(accessKeyID, secretAccessKey);
utility.UploadDirectory(directoryPath, existingBucketName);

The following C# code example uploads a directory to an Amazon S3 bucket. The example illustrates the use of various TransferUtility.UploadDirectory overloads to upload a directory, each successive call to upload replaces the previous upload. For instructions on how to create and test a working sample, see Testing the .NET Code Examples (p. 328)

```
using System;
using System.Configuration;
using Amazon.S3;
using Amazon.S3.Model;
using System.Collections.Specialized;
using Amazon.S3.Transfer;
using System.IO;
namespace s3.amazon.com.docsamples.highlevel_uploadDirectory
   class Program
       static string accessKeyID
                                         = "";
       static string secretAccessKey
        static string existingBucketName = "*** Provide bucket name ***";
        static string directoryPath = "*** Provide directory name ***";
        static void Main(string[] args)
            NameValueCollection appConfig = ConfigurationManager.AppSettings;
            accessKeyID = appConfig["AWSAccessKey"];
            secretAccessKey = appConfig["AWSSecretKey"];
             try
            {
                TransferUtility directoryTransferUtility =
                    new TransferUtility(accessKeyID, secretAccessKey);
                // 1. Upload a directory.
                directoryTransferUtility.UploadDirectory(directoryPath,
                                                         existingBucketName);
                Console.WriteLine("Upload statement 1 completed");
                // 2. Upload only the .txt files from a directory.
                     Also, search recursively.
                directoryTransferUtility.UploadDirectory(
                                               directoryPath,
                                               existingBucketName,
                                               "*.txt",
                                               SearchOption.AllDirectories);
                Console.WriteLine("Upload statement 2 completed");
                // 3. Same as 2 and some optional configuration
                     Search recursively for .txt files to upload).
                TransferUtilityUploadDirectoryRequest trUtilDirUpReq =
                    new TransferUtilityUploadDirectoryRequest()
                .WithBucketName(existingBucketName)
                .WithDirectory(directoryPath)
                .WithSearchOption(SearchOption.AllDirectories)
                .WithSearchPattern("*.txt");
```

Abort Multipart Uploads

The TransferUtility class provides a method, AbortMultipartUploads, to abort multipart uploads in progress. An upload is considered to be in-progress once you initiate it and until you complete it or abort it. You provide a DateTime value and this API aborts all the multipart uploads, on that bucket, that were initiated before the specified DateTime and in progress.

Because you are billed for all storage associated with uploaded parts (see Multipart Upload and Pricing (p. 107)), it is important that you either complete the multipart upload to have the object created or abort the multipart upload to remove any uploaded parts.

The following tasks guide you through using the high-level .NET classes to abort multipart uploads.

High-Level API Multipart Uploads Aborting Process

1	Create an instance of the TransferUtility class by providing your AWS credentials.
2	Execute the TransferUtility. AbortMultipartUploads method by passing the bucket name and a DateTime value.

The following C# code sample demonstrates the preceding tasks.

```
TransferUtility utility = new TransferUtility(accessKeyID, secretAccessKey);
utility.AbortMultipartUploads(existingBucketName, DateTime.Now.AddDays(-7));
```

The following C# code aborts all multipart uploads in progress that were initiated on a specific bucket over a week ago. For instructions on how to create and test a working sample, see Testing the .NET Code Examples (p. 328)

```
using System;
using System.Configuration;
using Amazon.S3;
using Amazon.S3.Model;
using System.Collections.Specialized;
using Amazon.S3.Transfer;
namespace s3.amazon.com.docsamples.highlevel_abortmultipartupload
   class Program
       static string accessKeyID
                                        = "";
       static string secretAccessKey
       static string existingBucketName = "***Provide bucket name***";
        static void Main(string[] args)
            NameValueCollection appConfig = ConfigurationManager.AppSettings;
            accessKeyID
                        = appConfig["AWSAccessKey"];
            secretAccessKey = appConfig["AWSSecretKey"];
            try
                TransferUtility transferUtility =
                   new TransferUtility(accessKeyID, secretAccessKey);
                // Aborting uploads that were initiated over a week ago.
                transferUtility.AbortMultipartUploads(
                    existingBucketName, DateTime.Now.AddDays(-7));
            }
            catch (AmazonS3Exception e)
                Console.WriteLine(e.Message, e.InnerException);
        }
    }
```



Note

You can also abort a specific multipart upload. For more information, see List Multipart Uploads (p. 159).

Track Multipart Upload Progress

The high-level multipart upload API provides an event,

TransferUtilityUploadRequest.UploadProgressEvent, to track the upload progress when uploading data using the TransferUtility class.

The event occurs periodically and returns multipart upload progress information such as the total number of bytes to transfer, and the number of bytes transferred at the time event occurred.

The following C# code sample demonstrates how you can subscribe to the UploadProgressEvent event and write a handler.

```
TransferUtility fileTransferUtility =
        new TransferUtility(accessKeyID, secretAccessKey);
// Use TransferUtilityUploadRequest to configure options.
// In this example we subscribe to an event.
TransferUtilityUploadRequest uploadRequest =
               new TransferUtilityUploadRequest()
               .WithBucketName(existingBucketName)
               .WithFilePath(filePath);
uploadRequest.UploadProgressEvent +=
         new EventHandler<UploadProgressArgs>(uploadRequest_UploadPartProgres
sEvent);
fileTransferUtility.Upload(uploadRequest);
static void uploadRequest_UploadPartProgressEvent(object sender, UploadProgres
sArgs e)
    // Process event.
    Console.WriteLine("{0}/{1}", e.TransferredBytes, e.TotalBytes);
}
```

The following C# code example uploads a file to an Amazon S3 bucket and tracks the progress by subscribing to the TransferUtilityUploadRequest.UploadProgressEvent event. For instructions on how to create and test a working sample, see Testing the .NET Code Examples (p. 328)

```
using System;
using System.Configuration;
using Amazon.S3;
using Amazon.S3.Model;
using System.Collections.Specialized;
using Amazon.S3.Transfer;
using System.IO;
namespace s3.amazon.com.docsamples.highlevel_trackprogress
    class Program
       static string accessKeyID
                                        = "";
       static string secretAccessKey
        static string existingBucketName = "*** Provide bucket name ***";
                                        = "*** Provide key name ***";
        static string keyName
       static string filePath
                                     = "*** Provide file to upload ***";
       static void Main(string[] args)
           NameValueCollection appConfig = ConfigurationManager.AppSettings;
           accessKeyID = appConfig["AWSAccessKey"];
           secretAccessKey = appConfig["AWSSecretKey"];
           try
                TransferUtility fileTransferUtility =
                   new TransferUtility(accessKeyID, secretAccessKey);
                // Use TransferUtilityUploadRequest to configure options.
                // In this example we subscribe to an event.
                TransferUtilityUploadRequest uploadRequest =
                   new TransferUtilityUploadRequest()
                    .WithBucketName(existingBucketName)
                    .WithFilePath(filePath);
                uploadRequest.UploadProgressEvent +=
                   new EventHandler<UploadProgressArgs>
                        (uploadRequest_UploadPartProgressEvent);
                fileTransferUtility.Upload(uploadRequest);
                Console.WriteLine("Upload completed");
            }
           catch (AmazonS3Exception e)
                Console.WriteLine(e.Message, e.InnerException);
        }
```

Using the Low-Level .NET API for Multipart Upload

Topics

- Upload a File (p. 155)
- List Multipart Uploads (p. 159)
- Track Multipart Upload Progress (p. 160)
- Abort a Multipart Upload (p. 160)

The AWS SDK for .NET exposes a low-level API that closely resembles the Amazon S3 REST API for multipart upload (see Using the REST API for Multipart Upload (p. 167)). Use the low-level API when you need to pause and resume multipart uploads, vary part sizes during the upload, or do not know the size of the data in advance. Use the high-level API (see Using the High-Level .NET API for Multipart Upload (p. 145)), whenever you don't have these requirements.

Upload a File

The following tasks guide you through using the low-level .NET classes to upload a file.

Low-Level API File UploadingProcess

1	Create an instance of the AmazonS3Client class, by providing your AWS credentials.
2	Initiate multipart upload by executing the AmazonS3Client.InitiateMultipartUpload method. You will need to provide information required to initiate the multipart upload by creating an instance of the InitiateMultipartUploadRequest class.
3	Save the Upload ID that the AmazonS3Client.InitiateMultipartUpload method returns. You will need to provide this upload ID for each subsequent multipart upload operation.
4	Upload the parts. For each part upload, execute the AmazonS3Client.UploadPart method. You will need to provide part upload information such as upload ID, bucket name, and the part number. You provide this information by creating an instance of the UploadPartRequest class.
5	Save the response of the AmazonS3Client.UploadPart method in a list. This response includes the ETag value and the part number you will later need to complete the multipart upload.
6	Repeat tasks 4 and 5 for each part.
7	Execute the AmazonS3Client.CompleteMultipartUpload method to complete the multipart upload.

The following C# code sample demonstrates the preceding tasks.

```
AmazonS3 s3Client = new AmazonS3Client(AccessKeyID, SecretAccessKey);
// List to store upload part responses.
List<UploadPartResponse> uploadResponses = new List<UploadPartResponse>();
// 1. Initialize.
InitiateMultipartUploadRequest initRequest =
   new InitiateMultipartUploadRequest()
   .WithBucketName(existingBucketName)
   .WithKey(keyName);
InitiateMultipartUploadResponse initResponse =
   s3Client.InitiateMultipartUpload(initRequest);
// 2. Upload Parts.
long contentLength = new FileInfo(filePath).Length;
long partSize = 5242880; // 5 MB
try
{
   long filePosition = 0;
   for (int i = 1; filePosition < contentLength; i++)</pre>
        // Create request to upload a part.
        UploadPartRequest uploadRequest = new UploadPartRequest()
            .WithBucketName(existingBucketName)
            .WithKey(keyName)
            .WithUploadId(initResponse.UploadId)
            .WithPartNumber(i)
            .WithPartSize(partSize)
            .WithFilePosition(filePosition)
            .WithFilePath(filePath);
        // Upload part and add response to our list.
        uploadResponses.Add(s3Client.UploadPart(uploadRequest));
        filePosition += partSize;
   }
   // Step 3: complete.
   CompleteMultipartUploadRequest compRequest =
       new CompleteMultipartUploadRequest()
        .WithBucketName(existingBucketName)
        .WithKey(keyName)
        .WithUploadId(initResponse.UploadId)
        .WithPartETags(uploadResponses);
   CompleteMultipartUploadResponse completeUploadResponse =
        s3Client.CompleteMultipartUpload(compRequest);
catch (Exception exception)
{
   Console.WriteLine("Exception occurred: {0}", exception.Message);
   s3Client.AbortMultipartUpload(new AbortMultipartUploadRequest()
```

```
.WithBucketName(existingBucketName)
.WithKey(keyName)
.WithUploadId(initResponse.UploadId));
}
```



Note

When uploading large objects using the .NET API, timeout might occur even while data is being written to the request stream. You can set explicit timeout using the UploadPartRequest.

The following C# code example uploads a file to an Amazon S3 bucket. For instructions on how to create and test a working sample, see Testing the .NET Code Examples (p. 328)

```
using System;
using System.Collections.Generic;
using System.Collections.Specialized;
using System.Configuration;
using System.IO;
using Amazon.S3;
using Amazon.S3.Model;
namespace s3.amazon.com.docsamples.LowLevel_UploadFromFile
    class Program
    {
        // Your AWS Credentials.
       static string AccessKeyID
                                        = "";
       static string SecretAccessKey
        static string existingBucketName = "*** Provide bucket name";
        static string keyName = "*** Provide object key ***";
        static string filePath = "*** Provide file to upload ***";
         static void Main(string[] args)
           NameValueCollection appConfig = ConfigurationManager.AppSettings;
            AccessKeyID = appConfig["AWSAccessKey"];
            SecretAccessKey = appConfig["AWSSecretKey"];
            AmazonS3 s3Client =
                new AmazonS3Client(AccessKeyID, SecretAccessKey);
            // List to store upload part responses.
            List<UploadPartResponse> uploadResponses =
                new List<UploadPartResponse>();
            // 1. Initialize.
            InitiateMultipartUploadRequest initiateRequest =
                new InitiateMultipartUploadRequest()
                .WithBucketName(existingBucketName)
                .WithKey(keyName);
            InitiateMultipartUploadResponse initResponse =
                s3Client.InitiateMultipartUpload(initiateRequest);
            // 2. Upload Parts.
            long contentLength = new FileInfo(filePath).Length;
            long partSize = 5 * (long)Math.Pow(2, 20); // 5 MB
            try
                long filePosition = 0;
                for (int i = 1; filePosition < contentLength; i++)</pre>
                    // Create request to upload a part.
```

```
UploadPartRequest uploadRequest = new UploadPartRequest()
            .WithBucketName(existingBucketName)
            .WithKey(keyName)
            .WithUploadId(initResponse.UploadId)
            .WithPartNumber(i)
            .WithPartSize(partSize)
            .WithFilePosition(filePosition)
            .WithFilePath(filePath);
        // Upload part and add response to our list.
        uploadResponses.Add(s3Client.UploadPart(uploadRequest));
        filePosition += partSize;
    }
    // Step 3: complete.
    CompleteMultipartUploadRequest completeRequest =
        new CompleteMultipartUploadRequest()
        .WithBucketName(existingBucketName)
        .WithKey(keyName)
        .WithUploadId(initResponse.UploadId)
        .WithPartETags(uploadResponses);
    CompleteMultipartUploadResponse completeUploadResponse =
        s3Client.CompleteMultipartUpload(completeRequest);
catch (Exception exception)
  Console.WriteLine("Exception occurred: {0}", exception.Message);
  s3Client.AbortMultipartUpload(new AbortMultipartUploadRequest()
        .WithBucketName(existingBucketName)
        .WithKey(keyName)
        .WithUploadId(initResponse.UploadId));
}
```

List Multipart Uploads

The following tasks guide you through using the low-level .NET classes to list all in-progress multipart uploads on a bucket.

Low-Level API Multipart Uploads Listing Process

1		Create an instance of the ListMultipartUploadsRequest class and provide the bucket name.
2	2	Execute the AmazonS3Client.ListMultipartUploads method. The method returns an instance of the ListMultipartUploadsResponse class, providing you the information about the in-progress multipart uploads.

The following C# code sample demonstrates the preceding tasks.

```
ListMultipartUploadsRequest allMultipartUploadsRequest = new ListMultipartUp
loadsRequest()
   .WithBucketName(existingBucketName);
ListMultipartUploadsResponse mpUploadsResponse = s3Client.ListMultipartUp
loads(allMultipartUploadsRequest);
```

Track Multipart Upload Progress

The low-level multipart upload API provides an event,

UploadPartRequest.UploadPartProgressEvent, to track the upload progress.

The event occurs periodically and returns multipart upload progress information such as the total number of bytes to transfer, and the number of bytes transferred at the time event occurred.

The following C# code sample demonstrates how you can subscribe to the UploadPartProgressEvent event and write a handler.

Abort a Multipart Upload

You can abort an in-progress multipart upload by calling the AmazonS3Client.AbortMultipartUpload method. This method deletes any parts that were uploaded to S3 and free up the resources. You must provide the upload ID, bucket name and the key name. The following C# code sample demonstrates how you can abort a multipart upload in progress.

```
s3Client.AbortMultipartUpload(new AbortMultipartUploadRequest()
   .WithBucketName(existingBucketName)
   .WithKey(keyName)
   .WithUploadId(uploadID));
```



Note

Instead of a specific multipart upload, you can abort all your in-progress multipart uploads initiated prior to a specific time. This clean up operation is useful to abort old multipart uploads that you initiated but neither completed or aborted. For more information, see Abort Multipart Uploads (p. 151).

Using the AWS SDK for PHP for Multipart Upload

Topics

- Using the High-Level PHP API for Multipart Upload (p. 161)
- Using the Low-Level PHP API for Multipart Upload (p. 162)

The AWS SDK for PHP provides support for the multipart upload API (see Uploading Objects Using Multipart Upload API (p. 134)).

High-level API

The high-level API simplifies the multipart upload flow. In just a few lines of code you can upload files to Amazon S3. This is recommended for simple file uploads.

Low-level API

The low-level APIs correspond to the multipart upload REST operations (see Using the REST API for Multipart Upload (p. 167)). Use the low-level API when you need to pause and resume multipart uploads, vary part sizes during the upload, or do not know the size of the data in advance. If you do not have these requirements, use the high-level API.

Using the High-Level PHP API for Multipart Upload

Topics

• Upload a File (p. 161)

The AWS SDK for PHP exposes a high-level method that simplifies the multipart upload flow (see Uploading Objects Using Multipart Upload API (p. 134)). You can upload data from a file or an open file stream. You can optionally set advanced options, such as the part size you want to use for the multipart upload, optional file metadata, the storage class (STANDARD or REDUCED_REDUNDANCY), or ACL.

Upload a File

The following tasks guide you through using the high-level PHP classes to upload a file.

High-Level API File Uploading Process

1	Create an instance of the AmazonS3 class by providing your AWS credentials.
2	Execute the AmazonS3::create_mpu_object() method.

The following PHP code sample demonstrates the preceding tasks.

```
// Instantiate the class
$s3 = new AmazonS3();

$response = $s3->create_mpu_object($bucket, $keyname, array(
    'fileUpload' => $filepath
));

print_r($response);
```

The following PHP example uploads a file to an Amazon S3 bucket. The example illustrates the use of the AmazonS3::create_mpu_object() method to upload a file. Each successive call to upload replaces the previous upload.

```
<?php
require_once '/path/to/sdk.class.php';
$bucket = '*** Provide your existing bucket name ***';
$keyname = '*** Provide object key ***';
$filepath = '*** Provide file to upload ***';
// Define a mebibyte
define('MB', 1048576);
// Instantiate the class
$s3 = new AmazonS3();
// 1. Upload file. Specify object key name explicitly.
$response = $s3->create_mpu_object($bucket, $keyname, array(
    'fileUpload' => $filepath
));
// Success?
header('Content-Type: text/plain; charset=utf-8');
print_r($response);
echo "Upload 1 completed!" . PHP_EOL . PHP_EOL;
// 2. Specify optional configuration.
$response = $s3->create_mpu_object($bucket, $keyname, array(
    'fileUpload' => $filepath,
    // Optional configuration
    'partSize' => 40*MB, // Defaults to 50MB
    'acl' => AmazonS3::ACL_PUBLIC,
    'storage' => AmazonS3::STORAGE_REDUCED,
    // Object metadata.
    'meta' => array(
        'param1' => 'value1',
        'param2' => 'value2',
     )
));
// Success?
print_r($response);
echo "Upload 2 completed!";
```

Using the Low-Level PHP API for Multipart Upload

Topics

- Upload a File (p. 163)
- List Multipart Uploads (p. 166)
- Abort a Multipart Upload (p. 166)

The AWS SDK for PHP exposes a low-level API that closely resembles the Amazon S3 REST API for multipart upload (see Using the REST API for Multipart Upload (p. 167)). Use the low-level API when you need to pause and resume multipart uploads, vary part sizes during the upload, or do not know the size of the data in advance. Use the high-level API (see Using the High-Level PHP API for Multipart Upload (p. 161)) whenever you don't have these requirements.

Upload a File

The following tasks guide you through using the low-level PHP classes to upload a file.

Low-Level API File UploadingProcess

1	Create an instance of the AmazonS3 class, by providing your AWS credentials.
2	Initiate multipart upload by executing the AmazonS3::initiate_multipart_upload() method. You need to provide the required information, i.e., bucket name and object key.
3	Retrieve the $UploadID$ from the response body. You will need to provide this upload ID for each subsequent multipart upload operation.
4	Call the AmazonS3::get_multipart_counts() to generate parts information. You need to provide the input file and the desired part size. The method returns an associative array of all the parts information, such as the part length and its starting position in the file.
5	Upload parts by executing the AmazonS3::upload_part() method. Save the response of each of the upload_part() methods in an array. Each response includes the ETag value you will later need to complete the multipart upload.
6	Execute the AmazonS3::complete_multipart_upload() method to complete the multipart upload.

The following PHP code sample demonstrates the preceding tasks.

```
// Instantiate the class.
$s3 = new AmazonS3();
// Define a megabyte
define('MB', 1048576);
// 1. Initiate a new multipart upload.
$response = $s3->initiate_multipart_upload($bucket, $keyname);
// Get the Upload ID.
$upload_id = (string) $response->body->UploadId;
// 2. Upload parts.
// Get part list for a given input file and given part size.
// Returns an associative array.
$parts = $s3->get_multipart_counts(filesize($filepath), 5*MB);
$responses = new CFArray(array());
foreach ($parts as $i => $part)
{
    // Upload part and save response in an array.
    $responses[] = $s3->upload_part($bucket, $keyname, $upload_id, array(
```

The following PHP code example uploads a file to an Amazon S3 bucket.

```
<?php
require_once '/path/to/sdk.class.php';
$bucket = '*** Provide your existing bucket name ***';
$keyname = '*** Provide object key name ***';
$filepath = '*** Provide file name to upload ***';
// Define a megabyte.
define('MB', 1048576);
// Instantiate the class
$s3 = new AmazonS3();
// 1. Initiate a new multipart upload. (Array parameter is optional)
$response = $s3->initiate_multipart_upload($bucket, $keyname, array(
    'acl' => AmazonS3::ACL_PUBLIC,
    'storage' => AmazonS3::STORAGE_REDUCED,
    'meta' => array(
        'param1' => 'value 1',
        'param2' => 'value 2',
        'param3' => 'value 3'
));
if (!$response->isOK())
{
    throw new S3_Exception('Bad!');
}
// Get the Upload ID.
$upload_id = (string) $response->body->UploadId;
// 2. Upload parts.
// Get part list for a given input file and given part size.
// Returns an associative array.
$parts = $s3->get_multipart_counts(filesize($filepath), 5*MB);
$responses = new CFArray(array());
foreach ($parts as $i => $part)
    // Upload part and save response in an array.
    $responses[] = $s3->upload_part($bucket, $keyname, $upload_id, array(
        'fileUpload' => $filepath,
        'partNumber' \Rightarrow ($i + 1),
        'seekTo' => (integer) $part['seekTo'],
        'length' => (integer) $part['length'],
    ));
// Verify that no part failed to upload, otherwise abort.
if (!$responses->areOK())
{
    // Abort an in-progress multipart upload
```

```
$response = $s3->abort_multipart_upload($bucket, $keyname, $upload_id);
    throw new S3_Exception('Failed!');
// 3. Complete the multipart upload. We need all part numbers and ETag values.
$parts = array();
foreach ($responses as $i => $response)
    $parts[] = array(
        'PartNumber' \Rightarrow ($i + 1),
        'ETag' => (string) $response->header['etag']
    );
$response = $s3->complete_multipart_upload(
                              $bucket, $keyname, $upload_id, $parts);
// Display the results
header('Content-Type: text/plain; charset=utf-8');
print_r($response);
if ($response->isOK())
{
    echo 'Object uploaded!';
```

List Multipart Uploads

The following tasks guide you through using the low-level PHP classes to list all in-progress multipart uploads on a bucket.

Low-Level API Multipart Uploads Listing Process

1	Create an instance of the AmazonS3 class.
2	Execute the AmazonS3::list_multipart_uploads() method by providing a bucket name. The method returns all of the in-progress multipart uploads on that bucket.

The following PHP code sample demonstrates the preceding tasks.

```
$s3 = new AmazonS3();
$response = $s3->list_multipart_uploads($bucket);
print_r($response);
```

Abort a Multipart Upload

You can abort a multipart upload that is in progress by calling the

AmazonS3::abort_multipart_upload() method. This method deletes any parts that were uploaded to S3 and frees up the resources. You must provide the upload ID, bucket name, and the object key to this method. The following PHP code sample demonstrates how you can abort a multipart upload in progress.

```
$s3 = new AmazonS3();
$response = $s3->abort_multipart_upload($bucket, $keyname, $upload_id);
print_r($response);
```

Using the REST API for Multipart Upload

The following sections in the Amazon Simple Storage Service API Reference describe the REST API for multipart upload.

- Initiate Multipart Upload
- Upload Part
- · Complete Multipart Upload
- Abort Multipart Upload
- List Parts
- List Multipart Uploads

You can use these APIs to make your own REST requests, or you can use one the SDKs we provide. For more information about the SDKs, see API Support for Multipart Upload (p. 108).

Uploading Objects Using Pre-Signed URLs

Topics

- Upload an Object Using Pre-Signed URL AWS SDK for Java (p. 168)
- Upload an Object Using Pre-Signed URL AWS SDK for .NET (p. 171)

A pre-signed URL gives you access to the object identified in the URL, provided that the creator of the pre-signed URL has permissions to access that object. That is, if you receive a pre-signed URL to upload an object, you can upload the object only if the creator of the pre-signed URL has the necessary permissions to upload that object.

All objects and buckets by default are private. The pre-signed URLs are useful if you want your user/customer to be able upload a specific object to you bucket, but you don't require them to have AWS security credentials or permissions. When you create a pre-signed URL, you must provide your security credentials, specify a bucket name an object key, an HTTP method (PUT of uploading objects) and an expiration date and time. The pre-signed URLs are valid only for the specified duration.

You can generate a pre-signed URL programmatically using the AWS SDK for Java or the AWS SDK for .NET. If you are using Visual Studio, you can also use the AWS Explorer to generate a pre-signed object URL without writing any code. Anyone who receives a valid pre-signed URL can then programmatically upload an object.

For more information, go to Using Amazon S3 from AWS Explorer.

For instructions about how to install the AWS Explorer, see Using the AWS SDKs and Explorers (p. 325).



Note

Anyone with valid security credentials can create a pre-signed URL. However, in order to successfully upload an object, the pre-signed URL must be created by someone who has permission to perform the operation that the pre-signed URL is based upon.

Upload an Object Using Pre-Signed URL - AWS SDK for Java

The following tasks guide you through using the Java classes to upload an object using a pre-signed URL.

Uploading Objects

1	Create an instance of the AmazonS3 class by providing your AWS credentials. These credentials are used in creating a signature for authentication when you generate a pre-signed URL.
2	Generate a pre-signed URL by executing the AmazonS3.generatePresignedUrl method. You provide a bucket name, an object key, and an expiration date by creating an instance of the GeneratePresignedUrlRequest class. You must specify the HTTP verb PUT when creating this URL if you want to use it to upload an object.
3	Anyone with the pre-signed URL can upload an object. The upload creates an object or replaces any existing object with the same key that is specified in the pre-signed URL.

The following Java code sample demonstrates the preceding tasks.

Amazon Simple Storage Service Developer Guide Uploading Objects Using Pre-Signed URLs

The following Java code example generates a pre-signed URL The example code then uses the pre-signed URL to upload sample data as an object. For instructions about how to create and test a working sample, see Testing the .NET Code Examples (p. 328)

```
import java.io.IOException;
import java.net.URL;
import com.amazonaws.AmazonClientException;
import com.amazonaws.AmazonServiceException;
import com.amazonaws.HttpMethod;
import com.amazonaws.auth.PropertiesCredentials;
import com.amazonaws.services.s3.AmazonS3;
import com.amazonaws.services.s3.AmazonS3Client;
import com.amazonaws.services.s3.model.GeneratePresignedUrlRequest;
import java.net.*;
import java.io.*;
public class S3Sample {
private static String bucketName = "ExampleBucket";
private static String objectKey = "JavaObj.xml";
public static void main(String[] args) throws IOException {
 AmazonS3 s3client = new AmazonS3Client(new PropertiesCredentials(
  S3Sample.class.getResourceAsStream("AwsCredentials.properties")));
 try {
  System.out.println("Generating pre-signed URL.");
   java.util.Date expiration = new java.util.Date();
  long milliSeconds = expiration.getTime();
  milliSeconds += 1000 * 60 * 60; // Add 1 hour.
  expiration.setTime(milliSeconds);
  GeneratePresignedUrlRequest generatePresignedUrlRequest =
       new GeneratePresignedUrlRequest(bucketName, objectKey);
  generatePresignedUrlRequest.setMethod(HttpMethod.PUT);
  generatePresignedUrlRequest.setExpiration(expiration);
  URL url = s3client.generatePresignedUrl(generatePresignedUrlRequest);
  UploadObject(url);
  System.out.println("Pre-Signed URL = " + url.toString());
  } catch (AmazonServiceException exception) {
   System.out.println("Caught an AmazonServiceException, " +
     "which means your request made it " +
     "to Amazon S3, but was rejected with an error response " +
   "for some reason.");
  System.out.println("Error Message: " + exception.getMessage());
  System.out.println("HTTP Code: " + exception.getStatusCode());
  System.out.println("AWS Error Code:" + exception.getErrorCode());
  System.out.println("Error Type: " + exception.getErrorType());
                                      " + exception.getRequestId());
  System.out.println("Request ID:
  } catch (AmazonClientException ace) {
  System.out.println("Caught an AmazonClientException, " +
     "which means the client encountered " +
     "an internal error while trying to communicate" +
```

Amazon Simple Storage Service Developer Guide Uploading Objects Using Pre-Signed URLs

```
" with S3, " +
   "such as not being able to access the network.");
System.out.println("Error Message: " + ace.getMessage());
}

public static void UploadObject(URL url) throws IOException
{
   HttpURLConnection connection=(HttpURLConnection) url.openConnection();
   connection.setDoOutput(true);
   connection.setRequestMethod("PUT");
OutputStreamWriter out = new OutputStreamWriter(
      connection.getOutputStream());
   out.write("This text uploaded as object.");
   out.close();
   int responseCode = connection.getResponseCode();
}
```

Upload an Object Using Pre-Signed URL - AWS SDK for .NET

The following tasks guide you through using the .NET classes to upload an object using a pre-signed URL.

Downloading Objects

1	Create an instance of the AmazonS3 class by providing your AWS credentials. These credentials are used in creating a signature for authentication when you generate a pre-signed URL.
2	Generate a pre-signed URL by executing the AmazonS3.GetPreSignedURL method. You provide a bucket name, an object key, and an expiration date by creating an instance of the GetPreSignedUrlRequest class. You must specify the HTTP verb PUT when creating this URL if you plan to use it to upload an object.
3	Anyone with the pre-signed URL can upload an object. You can create an instance of the HttpWebRequest class by providing the pre-signed URL and uploading the object.

The following C# code sample demonstrates the preceding tasks.

Amazon Simple Storage Service Developer Guide Uploading Objects Using Pre-Signed URLs

```
HttpWebRequest httpRequest = WebRequest.Create(url) as HttpWebRequest;
httpRequest.Method = "PUT";
using (Stream dataStream = httpRequest.GetRequestStream())
{
    // Upload object.
}
HttpWebResponse response = httpRequest.GetResponse() as HttpWebResponse;
```

The following C# code example generates a pre-signed URL for a specific object and uses it to upload a file. For instructions about how to create and test a working sample, see Testing the .NET Code Examples (p. 328)

```
using System;
using System.Configuration;
using System.Collections.Specialized;
using Amazon.S3;
using Amazon.S3.Model;
using System.Net;
using System.IO;
namespace s3.amazon.com.docsamples.putobjectusingpresignedurl
    class S3Sample
       static AmazonS3 s3Client;
        // File to upload.
        static string filePath = @"*** Specify file to upload ***";
        // Information to generate pre-signed object URL.
        static string bucketName = "*** Provide bucket name ***";
        static string objectKey = "*** Provide object key for the new object
***";
       public static void Main(string[] args)
            NameValueCollection appConfig = ConfigurationManager.AppSettings;
            string accessKeyID = appConfig["AWSAccessKey"];
            string secretAccessKeyID = appConfig["AWSSecretKey"];
            try
               using (s3Client = Amazon.AWSClientFactory.CreateAmazonS3Client(
                     accessKeyID, secretAccessKeyID))
                    string url = GeneratePreSignedURL();
                    UploadObject(url);
            catch (AmazonS3Exception amazonS3Exception)
                if (amazonS3Exception.ErrorCode != null &&
                    (amazonS3Exception.ErrorCode.Equals("InvalidAccessKeyId")
                    amazonS3Exception.ErrorCode.Equals("InvalidSecurity")))
                    Console.WriteLine("Check the provided AWS Credentials.");
                    Console.WriteLine(
                    "To sign up for service, go to http://aws.amazon.com/s3");
                }
                else
```

```
Console.WriteLine(
                     "Error occurred. Message: '{0}' when listing objects",
                     amazonS3Exception.Message);
            catch (Exception e)
                Console.WriteLine(e.Message);
            Console.WriteLine("Press any key to continue...");
            Console.ReadKey();
       static void UploadObject(string url)
            HttpWebRequest httpRequest = WebRequest.Create(url) as HttpWebRe
quest;
            httpRequest.Method = "PUT";
            using (Stream dataStream = httpRequest.GetRequestStream())
                byte[] buffer = new byte[8000];
                using (FileStream fileStream = new FileStream(filePath,
FileMode.Open, FileAccess.Read))
                    int bytesRead = 0;
                    while ((bytesRead = fileStream.Read(buffer, 0, buf
fer.Length)) > 0)
                        dataStream.Write(buffer, 0, bytesRead);
                }
           HttpWebResponse response = httpRequest.GetResponse() as HttpWebRe
sponse;
        static string GeneratePreSignedURL()
            GetPreSignedUrlRequest request = new GetPreSignedUrlRequest();
            request.WithBucketName(bucketName);
            request.WithKey(objectKey);
            request.Verb = HttpVerb.PUT; // This is the default.
            request.WithExpires(DateTime.Now.AddMinutes(5));
            string url = null;
                url = s3Client.GetPreSignedURL(request);
            return url;
   }
```

Copying Objects

Topics

- Related Resources (p. 175)
- Copying Objects in a Single Operation (p. 175)
- · Copying Objects Using the Multipart Upload API (p. 185)

The copy operation creates a copy of an object that is already stored in Amazon S3. You can create a copy of your object up to 5 GB in a single atomic operation. However, for copying an object that is greater than 5 GB, you must use the multipart upload API. Using the copy operation, you can:

- · Create additional copies of objects
- Rename objects by copying them and deleting the original ones
- Move objects across Amazon S3 locations (e.g., Northern California and EU)



Note

Copying objects across locations incurs bandwidth charges.

Related Resources

• Using the AWS SDKs and Explorers (p. 325)

Copying Objects in a Single Operation

Topics

- Copy an Object Using the AWS SDK for Java (p. 175)
- · Copy an Object Using the AWS SDK for .NET (p. 177)
- Copy an Object Using the AWS SDK for PHP (p. 180)
- Copy an Object Using the AWS SDK for Ruby (p. 183)
- Copy an Object Using the REST API (p. 184)

The examples in this section show how to copy objects up to 5 GB in a single operation. For copying objects greater than 5 GB, you must use multipart upload API. For more information, see Copying Objects Using the Multipart Upload API (p. 185).

Copy an Object Using the AWS SDK for Java

The following tasks guide you through using the Java classes to copy an object in Amazon S3.

Copying Objects

1 Create an instance of the AmazonS3Client class by providing your AWS credentials.

Amazon Simple Storage Service Developer Guide Copying Objects in a Single Operation

Execute one of the Amazons3Client.copyObject methods. You need to provide the request information, such as source bucket name, source key name, destination bucket name, and destination key. You provide this information by creating an instance of the CopyObjectRequest class or optionally providing this information directly with the Amazons3Client.copyObject method.

The following Java code sample demonstrates the preceding tasks.

The following Java code example makes a copy of an object. The copied object with a different key is saved in the same source bucket. For instructions on how to create and test a working sample, see Testing the Java Code Examples (p. 327)

```
import java.io.IOException;
import com.amazonaws.AmazonClientException;
import com.amazonaws.AmazonServiceException;
import com.amazonaws.auth.PropertiesCredentials;
import com.amazonaws.services.s3.AmazonS3;
import com.amazonaws.services.s3.AmazonS3Client;
import com.amazonaws.services.s3.model.CopyObjectRequest;
private static String key = "*** Provide bucket name ***";

private static String key = "*** Provide bucket name ***";
public class S3Sample {
private static String destinationKey = "*** Provide dest. key ***";
    public static void main(String[] args) throws IOException {
        AmazonS3 s3client = new AmazonS3Client(new PropertiesCredentials(
                S3Sample.class.getResourceAsStream(
                  "AwsCredentials.properties")));
        try {
            // Copying object
            CopyObjectRequest copyObjRequest = new CopyObjectRequest(
              bucketName, key, bucketName, destinationKey);
            System.out.println("Copying object.");
            s3client.copyObject(copyObjRequest);
        } catch (AmazonServiceException ase) {
            System.out.println("Caught an AmazonServiceException, " +
              "which means your request made it " +
              "to Amazon S3, but was rejected with an error " +
                    "response for some reason.");
            System.out.println("Error Message: " + ase.getMessage());
            System.out.println("HTTP Status Code: " + ase.getStatusCode());
            System.out.println("AWS Error Code: " + ase.getErrorCode());
                                                   " + ase.getErrorType());
            System.out.println("Error Type:
            System.out.println("Request ID:
                                                   " + ase.getRequestId());
        } catch (AmazonClientException ace) {
            System.out.println("Caught an AmazonClientException, " +
              "which means the client encountered " +
                    "an internal error while trying to " +
                     " communicate with S3, " +
                    "such as not being able to access the network.");
            System.out.println("Error Message: " + ace.getMessage());
    }
```

Copy an Object Using the AWS SDK for .NET

The following tasks guide you through using the high-level .NET classes to upload a file. The API provides several variations, *overloads*, of the Upload method to easily upload your data.

Amazon Simple Storage Service Developer Guide Copying Objects in a Single Operation

Copying Objects

1	Create an instance of the AmazonS3 class by providing your AWS credentials.			
2	Execute one of the AmazonS3.CopyObject. You need to provide information such as source bucket, source key name, target bucket, and target key name. You provide this information by creating an instance of the CopyObjectRequest class.			

The following C# code sample demonstrates the preceding tasks.

The following C# code example makes a copy of an object in the same source bucket. The example illustrates the use of the AmazonS3.CopyObject method. For instructions on how to create and test a working sample, see Testing the .NET Code Examples (p. 328)

```
using System;
using System.Configuration;
using System.Collections.Specialized;
using Amazon.S3;
using Amazon.S3.Model;
namespace s3.amazon.com.docsamples.copyobject
   class S3Sample
       static string bucketName = "*** Provide bucket name ***";
       static string keyName = "*** Provide key name ***";
       static string destKeyName = "*** Provide destination key name ***";
        static AmazonS3 client;
       public static void Main(string[] args)
            if (checkRequiredFields())
            {
                NameValueCollection appConfig =
                    ConfigurationManager.AppSettings;
                string accessKeyID = appConfig["AWSAccessKey"];
                string secretAccessKeyID = appConfig["AWSSecretKey"];
                using (client = Amazon.AWSClientFactory.CreateAmazonS3Client(
                    accessKeyID, secretAccessKeyID))
                {
                    Console.WriteLine("Copying an object");
                    CopyingObject();
                }
            }
            Console.WriteLine("Press any key to continue...");
            Console.ReadKey();
        static bool checkRequiredFields()
            NameValueCollection appConfig = ConfigurationManager.AppSettings;
            if (string.IsNullOrEmpty(appConfig["AWSAccessKey"]))
                Console.WriteLine(
                    "AWSAccessKey was not set in the App.config file.");
                return false;
            if (string.IsNullOrEmpty(appConfig["AWSSecretKey"]))
                Console.WriteLine(
                    "AWSSecretKey was not set in the App.config file.");
```

```
return false;
        if (string.IsNullOrEmpty(bucketName))
            Console.WriteLine("The variable bucketName is not set.");
            return false;
        if (string.IsNullOrEmpty(keyName))
            Console.WriteLine("The variable keyName is not set.");
            return false;
        return true;
    static void CopyingObject()
        try
            // simple object put
            CopyObjectRequest request = new CopyObjectRequest();
            request.SourceBucket = bucketName;
            request.SourceKey = keyName;
            request.DestinationBucket = bucketName;
            request.DestinationKey = destKeyName;
            S3Response response = client.CopyObject(request);
            response.Dispose();
        catch (AmazonS3Exception s3Exception)
            Console.WriteLine(s3Exception.Message,
                              s3Exception.InnerException);
    }
}
```

Copy an Object Using the AWS SDK for PHP

The following tasks guide you through using the PHP classes to copy an object within Amazon S3, from one bucket to another or to copy an object within the same bucket.

Copying Objects

1	Create an instance of the AmazonS3 class by providing your AWS credentials.
2	To copy an object, execute the AmazonS3::copy_object() low-level method. You need to provide information such as source bucket, source key name, target bucket, and target key name. You provide this information as a ComplexType parameter, where a ComplexType is a set of key-value pairs.
	If you want to copy several objects, you can optionally execute these requests in parallel by adding the <code>copy_object</code> requests to the batch queue and executing the batch by calling the <code>batch.send()</code> method.

Amazon Simple Storage Service Developer Guide Copying Objects in a Single Operation

The following PHP code sample demonstrates the preceding tasks.

```
// Instantiate the class.
$s3 = new AmazonS3();
// 1. Copy one object.
$response = $s3->copy_object(array( // Source.
                               'bucket' => $sourcebucket,
                               'filename' => $sourcekeyname
                             ),
                             array( // Target.
                               'bucket' => $targetbucket,
                               'filename' => $targetkeyname
);
// 2. Copy objects using batch.
$s3->batch()->copy_object(array( // Source.
                            'bucket' => $sourcebucket,
                            'filename' => $sourcekeyname
                         array( // Target.
                           'bucket' => $targetbucket,
                            'filename' => $targetkeyname
);
$s3->batch()->copy_object(array( // Source.
                            'bucket' => $sourcebucket,
                            'filename' => $sourcekeyname
                         array( // Target.
                            'bucket' => $targetbucket,
                             'filename' => $targetkeyname
);
$responses = $s3->batch()->send();
```

The following PHP example illustrates the use of the <code>copy_object()</code> method to copy the single object. First, the example copies a single object. The example then illustrates the use of the batch operation, where it adds two <code>copy_object()</code> requests to the batch, and later sends the batch for parallel execution.

```
<?php
require_once '../aws-sdk-for-php/sdk.class.php';
$sourcebucket = '*** Source bucket ***';
$sourcekeyname = '*** Source object key name ***';
$targetbucket = '*** Target bucket ***';
$targetkeyname = '*** Target object key name ***';
// Instantiate the class.
$s3 = new AmazonS3();
// Copy object.
$response = $s3->copy_object(array( // Source.
                               'bucket' => $sourcebucket,
                               'filename' => $sourcekeyname
                            array( // Target.
                               'bucket' => $targetbucket,
                               'filename' => $targetkeyname
);
// Success?
print_r($response->isOK());
// Add copy_object request to the batch to execute in parallel later.
$s3->batch()->copy_object(array( // Source.
                             'bucket' => $sourcebucket,
                             'filename' => $sourcekeyname
                          ),
                          array( // Target.
                             'bucket' => $targetbucket,
                             'filename' => $targetkeyname
                          )
);
$s3->batch()->copy_object(array( // Source.
                            'bucket' => $sourcebucket,
                            'filename' => $sourcekeyname
                          array( // Target.
                            'bucket' => $targetbucket,
                            'filename' => $targetkeyname
);
$responses = $s3->batch()->send();
if ($responses->areOK())
{
    //...
```

Copy an Object Using the AWS SDK for Ruby

The following tasks guide you through using the Ruby classes to copy an object in Amazon S3, from one bucket to another or to copy an object within the same bucket.

Copying Objects

1	Create an instance of the AWS::S3 class by providing your AWS credentials.			
2	Execute either the AWS::S3::S3Object#copy_to or AWS::S3::S3Object#copy_from method. You need to provide the request information, such as source bucket name, source key name, destination bucket name, and destination key.			

The following Ruby code sample demonstrates the preceding tasks using the #copy_to method to copy an object from one bucket to another.

```
# Upload a file and set server-side encryption.
bucket1 = s3.buckets[source_bucket]
bucket2 = s3.buckets[target_bucket]
obj1 = bucket1.objects[source_key]
obj2 = bucket2.objects[target_key]
obj1.copy_to(obj2)
```

Example

The following Ruby script example makes a copy of an object using the #copy_from method. The copied object with a different key is saved in the same source bucket. For instructions about how to create and test a working sample, see Using the AWS SDK for Ruby (p. 329).

```
#!/usr/bin/env ruby
require 'rubygems'
require 'aws-sdk'

AWS.config(
    :access_key_id => '*** Provide access key ***',
    :secret_access_key => '*** Provide secret key ***'
)

bucket_name = '*** Provide bucket name ***'
source_key = '*** Provide source key ***'
target_key = '*** Provide target key ***'

# Get an instance of the S3 interface.
s3 = AWS::S3.new

# Copy the object.
s3.buckets[bucket_name].objects[target_key].copy_from(source_key)
puts "Copying file #{source_key} to #{target_key}."
```

Copy an Object Using the REST API

This example describes how to copy an object using REST. For more information about the REST API, go to PUT Object (Copy).

This example copies the flotsam object from the pacific bucket to the jetsam object of the atlantic bucket, preserving its metadata.

```
PUT /jetsam HTTP/1.1
Host: atlantic.s3.amazonaws.com
x-amz-copy-source: /pacific/flotsam
Authorization: AWS 15B4D3461F177624206A:ENoSbxYByFA0UGLZUqJN5EUnLDg=
Date: Wed, 20 Feb 2008 22:12:21 +0000
```

The signature was generated from the following information.

```
PUT\r\n
\r\n
\r\n
Wed, 20 Feb 2008 22:12:21 +0000\r\n
x-amz-copy-source:/pacific/flotsam\r\n
/atlantic/jetsam
```

Amazon S3 returns the following response that specifies the ETag of the object and when it was last modified.

Copying Objects Using the Multipart Upload API

Topics

- Copy an Object Using the AWS SDK for Java Multipart Upload API (p. 185)
- Copy an Object Using the AWS SDK for .NET Multipart Upload API (p. 188)
- · Copy Object Using the REST Multipart Upload API (p. 193)

The examples in this section show you how to copy objects greater than 5 GB using the multipart upload API. You can copy objects less than 5 GB in a single operation. For more information, see Copying Objects in a Single Operation (p. 175).

Copy an Object Using the AWS SDK for Java Multipart Upload API

The following task guides you through using the Java SDK to copy an Amazon S3 object from one source location to another, such as from one bucket to another. You can use the code demonstrated here to copy objects greater than 5 GB. For objects less than 5 GB, use the single operation copy described in Copy an Object Using the AWS SDK for Java (p. 175).

Copying Objects

1	Create an instance of the AmazonS3Client class by providing your AWS credentials.			
2	Initiate a multipart copy by executing the AmazonS3Client.initiateMultipartUpload method. Create an instance of InitiateMultipartUploadRequest. You will need to provide a bucket name and a key name.			
3	Save the upload ID from the response object that the <pre>https://document.initiateMultipartUpload method returns. You will need to provide this upload ID for each subsequent multipart upload operation.</pre>			
4	Copy all the parts. For each part copy, create a new instance of the CopyPartRequest class and provide part information including source bucket, destination bucket, object key, uploadID, first byte of the part, last byte of the part, and the part number.			
5	Save the response of the CopyPartRequest method in a list. The response includes the ETag value and the part number. You will need the part number to complete the multipart upload.			
6	Repeat tasks 4 and 5 for each part.			
7	Execute the AmazonS3Client.completeMultipartUpload method to complete the copy.			

The following Java code sample demonstrates the preceding tasks.

```
// Step 1: Create instance and provide credentials.
AmazonS3Client s3Client = new AmazonS3Client(new
    PropertiesCredentials(
        LowLevel_LargeObjectCopy.class.getResourceAsStream(
        "AwsCredentials.properties")));
```

```
// Create lists to hold copy responses
List<CopyPartResult> copyResponses =
        new ArrayList<CopyPartResult>();
// Step 2: Initialize
InitiateMultipartUploadRequest initiateRequest =
       new InitiateMultipartUploadRequest(targetBucketName, targetObjectKey);
InitiateMultipartUploadResult initResult =
        s3Client.initiateMultipartUpload(initiateRequest);
// Step 3: Save upload Id.
String uploadId = initResult.getUploadId();
try {
    // Get object size.
    GetObjectMetadataRequest metadataRequest =
    new GetObjectMetadataRequest(sourceBucketName, sourceObjectKey);
   ObjectMetadata metadataResult = s3Client.getObjectMetadata(metadataRequest);
   long objectSize = metadataResult.getContentLength(); // in bytes
    // Step 4. Copy parts.
   long partSize = 5 * (long)Math.pow(2.0, 20.0); // 5 MB
   long bytePosition = 0;
    for (int i = 1; bytePosition < objectSize; i++)</pre>
        // Step 5. Save copy response.
    CopyPartRequest copyRequest = new CopyPartRequest()
           .withDestinationBucketName(targetBucketName)
           .withDestinationKey(targetObjectKey)
           .withSourceBucketName(sourceBucketName)
           .withSourceKey(sourceObjectKey)
           .withUploadId(initResult.getUploadId())
           .withFirstByte(bytePosition)
           .withLastByte(((bytePosition + partSize) > objectSize) ?
             (bytePosition + (objectSize - bytePosition) - 1) : (bytePosition
+ partSize))
           .withPartNumber(i);
        copyResponses.add(s3Client.copyPart(copyRequest));
       bytePosition += partSize;
    // Step 7. Complete copy operation.
    CompleteMultipartUploadResult completeUploadResponse =
        s3Client.completeMultipartUpload(completeRequest);
} catch (Exception e) {
    System.out.println(e.getMessage());
```

The following Java code example copies an object from one Amazon S3 bucket to another. For instructions on how to create and test a working sample, see Testing the Java Code Examples (p. 327).

```
import java.io.IOException;
import java.util.ArrayList;
import java.util.List;
import com.amazonaws.auth.PropertiesCredentials;
import com.amazonaws.services.s3.*;
import com.amazonaws.services.s3.model.*;
public class LowLevel_LargeObjectCopy {
   public static void main(String[] args) throws IOException {
        String sourceBucketName = "*** Source-Bucket-Name ***";
        String targetBucketName = "*** Target-Bucket-Name ***";
        String sourceObjectKey = "*** Source-Object-Key ***";
        String targetObjectKey = "*** Target-Object-Key ***";
        AmazonS3Client s3Client = new AmazonS3Client(new
          PropertiesCredentials(
            LowLevel_LargeObjectCopy.class.getResourceAsStream(
              "AwsCredentials.properties")));
        // List to store copy part responses.
       List<CopyPartResult> copyResponses =
                 new ArrayList<CopyPartResult>();
        InitiateMultipartUploadRequest initiateRequest =
        new InitiateMultipartUploadRequest(targetBucketName, targetObjectKey);
        InitiateMultipartUploadResult initResult =
         s3Client.initiateMultipartUpload(initiateRequest);
        try {
            // Get object size.
            GetObjectMetadataRequest metadataRequest =
             new GetObjectMetadataRequest(sourceBucketName, sourceObjectKey);
          ObjectMetadata metadataResult = s3Client.getObjectMetadata(metadataRe
quest);
            long objectSize = metadataResult.getContentLength(); // in bytes
            // Copy parts.
            long partSize = 5 * (long)Math.pow(2.0, 20.0); // 5 MB
            long bytePosition = 0;
            for (int i = 1; bytePosition < objectSize; i++)</pre>
             CopyPartRequest copyRequest = new CopyPartRequest()
                   .withDestinationBucketName(targetBucketName)
                   .withDestinationKey(targetObjectKey)
                   .withSourceBucketName(sourceBucketName)
                   .withSourceKey(sourceObjectKey)
```

```
.withUploadId(initResult.getUploadId())
                   .withFirstByte(bytePosition)
                   .withLastByte(((bytePosition + partSize) > objectSize) ?
                     (bytePosition + (objectSize - bytePosition) - 1) : (byte
Position + partSize))
                   .withPartNumber(i);
                copyResponses.add(s3Client.copyPart(copyRequest));
                bytePosition += partSize;
            CompleteMultipartUploadRequest completeRequest = new
             CompleteMultipartUploadRequest(
               targetBucketName,
               targetObjectKey,
               initResult.getUploadId(),
               GetETags(copyResponses));
            CompleteMultipartUploadResult completeUploadResponse =
                s3Client.completeMultipartUpload(completeRequest);
        } catch (Exception e) {
         System.out.println(e.getMessage());
     }
    // Helper function that constructs ETags.
    static List<PartETag> GetETags(List<CopyPartResult> responses)
    {
       List<PartETag> etags = new ArrayList<PartETag>();
        for (CopyPartResult response : responses)
            etags.add(new PartETag(response.getPartNumber(), re
sponse.getETag()));
        }
        return etags;
```

Copy an Object Using the AWS SDK for .NET Multipart Upload API

The following task guides you through using the .NET SDK to copy an Amazon S3 object from one source location to another, such as from one bucket to another. You can use the code demonstrated here to copy objects that are greater than 5 GB. For objects less than 5 GB, use the single operation copy described in Copy an Object Using the AWS SDK for .NET (p. 177).

Copying Objects

1	Create an instance of the AmazonS3Client class by providing your AWS credentials.			
2	Initiate a multipart copy by executing the AmazonS3Client.InitiateMultipartUpload method. Create an instance of the InitiateMultipartUploadRequest. You will need to provide a bucket name and key name.			

Amazon Simple Storage Service Developer Guide Copying Objects Using the Multipart Upload API

3	Save the upload ID from the response object that the AmazonS3Client.InitiateMultipartUpload method returns.You will need to provide this upload ID for each subsequent multipart upload operation.			
4	Copy all the parts. For each part copy, create a new instance of the CopyPartRequest class and provide part information including source bucket, destination bucket, object key, uploadID, first byte of the part, last byte of the part, and the part number.			
5	Save the response of the CopyPartRequest method in a list. The response includes the ETag value and the part number you will need to complete the multipart upload.			
6	Repeat tasks 4 and 5 for each part.			
7	Execute the AmazonS3Client.CompleteMultipartUpload method to complete the copy.			

The following C# code sample demonstrates the preceding tasks.

```
// Step 1. Create instance and provide credentials.
AmazonS3Config config = new AmazonS3Config();
AmazonS3 s3Client = new AmazonS3Client(AccessKeyID, SecretAccessKey, config);
// List to store upload part responses.
List<UploadPartResponse> uploadResponses =
    new List<UploadPartResponse>();
List<CopyPartResponse> copyResponses =
   new List<CopyPartResponse>();
InitiateMultipartUploadRequest initiateRequest =
   new InitiateMultipartUploadRequest()
        .WithBucketName(targetBucket)
        .WithKey(targetObjectKey);
// Step 2. Initialize.
InitiateMultipartUploadResponse initResponse =
s3Client.InitiateMultipartUpload(initiateRequest);
// Step 3. Save Upload Id.
String uploadId = initResponse.UploadId;
try
{
    // Get object size.
   GetObjectMetadataRequest metadataRequest = new GetObjectMetadataRequest();
    metadataRequest.BucketName = sourceBucket;
    metadataRequest.Key = sourceObjectKey;
    GetObjectMetadataResponse metadataResponse = s3Client.GetObject
Metadata(metadataRequest);
    long objectSize = metadataResponse.ContentLength; // in bytes
    // Step 4. Copy parts.
    long partSize = 5 * (long)Math.Pow(2, 20); // 5 MB
    long bytePosition = 0;
    for (int i = 1; bytePosition < objectSize; i++)</pre>
```

```
{
        // Step 5. Save copy response.
       CopyPartRequest copyRequest = new CopyPartRequest()
            .WithDestinationBucket(targetBucket)
            .WithDestinationKey(targetObjectKey)
            .WithSourceBucket(sourceBucket)
            .WithSourceKey(sourceObjectKey)
            .WithUploadID(uploadId)
            .WithFirstByte(bytePosition)
            .WithLastByte(((bytePosition + partSize) > objectSize) ?
            (bytePosition + (objectSize - bytePosition) - 1) : (bytePosition
+ partSize))
            .WithPartNumber(i);
        copyResponses.Add(s3Client.CopyPart(copyRequest));
       bytePosition += partSize;
     // Step 7. Complete copy operation.
    CompleteMultipartUploadRequest completeRequest =
       new CompleteMultipartUploadRequest()
            .WithBucketName(targetBucket)
            .WithKey(targetObjectKey)
            .WithUploadId(initResponse.UploadId)
            .WithPartETags(GetETags(copyResponses));
    CompleteMultipartUploadResponse completeUploadResponse =
        s3Client.CompleteMultipartUpload(completeRequest);
}
catch (Exception e) {
   Console.WriteLine(e.Message);
```

The following C# code example copies an object from one Amazon S3 bucket to another. For instructions on how to create and test a working sample, see Testing the .NET Code Examples (p. 328).

```
using System;
using System.Collections.Generic;
using System.Collections.Specialized;
using System.Configuration;
using System.IO;
using Amazon.S3;
using Amazon.S3.Model;
namespace s3.amazon.com.docsamples.LowLevel_LargeObjectCopy
    class CopyingObjectsUsingMPU
        static string sourceBucket
                                     = "*** Source-Bucket ***";
        static string targetBucket = "*** Target-Bucket ****";
        static string sourceObjectKey = "*** Source-Object-Key ***";
        static string targetObjectKey = "*** Target-Object-Key ***";
        static void Main(string[] args)
            NameValueCollection appConfig = ConfigurationManager.AppSettings;
            AccessKeyID = appConfig["AWSAccessKey"];
            SecretAccessKey = appConfig["AWSSecretKey"];
            AmazonS3Config config = new AmazonS3Config();
          AmazonS3 s3Client = new AmazonS3Client(AccessKeyID, SecretAccessKey,
config);
            // List to store upload part responses.
            List<UploadPartResponse> uploadResponses =
                new List<UploadPartResponse>();
            List<CopyPartResponse> copyResponses =
                      new List<CopyPartResponse>();
            InitiateMultipartUploadRequest initiateRequest =
                   new InitiateMultipartUploadRequest()
                    .WithBucketName(targetBucket)
                    .WithKey(targetObjectKey);
            InitiateMultipartUploadResponse initResponse =
                s3Client.InitiateMultipartUpload(initiateRequest);
            String uploadId = initResponse.UploadId;
            try
                // Get object size.
                GetObjectMetadataRequest metadataRequest = new GetObject
MetadataRequest();
                metadataRequest.BucketName = sourceBucket;
                metadataRequest.Key = sourceObjectKey;
              GetObjectMetadataResponse metadataResponse = s3Client.GetObject
```

```
Metadata(metadataRequest);
                long objectSize = metadataResponse.ContentLength; // in bytes
                // Copy parts.
                long partSize = 5 * (long)Math.Pow(2, 20); // 5 MB
                long bytePosition = 0;
                for (int i = 1; bytePosition < objectSize; i++)</pre>
                    CopyPartRequest copyRequest = new CopyPartRequest()
                       .WithDestinationBucket(targetBucket)
                       .WithDestinationKey(targetObjectKey)
                       .WithSourceBucket(sourceBucket)
                       .WithSourceKey(sourceObjectKey)
                       .WithUploadID(uploadId)
                       .WithFirstByte(bytePosition)
                       .WithLastByte(((bytePosition + partSize) > objectSize)
                       (bytePosition + (objectSize - bytePosition) - 1) :
(bytePosition + partSize))
                       .WithPartNumber(i);
                    copyResponses.Add(s3Client.CopyPart(copyRequest));
                    bytePosition += partSize;
                CompleteMultipartUploadRequest completeRequest =
                      new CompleteMultipartUploadRequest()
                         .WithBucketName(targetBucket)
                         .WithKey(targetObjectKey)
                         .WithUploadId(initResponse.UploadId)
                         .WithPartETags(GetETags(copyResponses));
                CompleteMultipartUploadResponse completeUploadResponse =
                    s3Client.CompleteMultipartUpload(completeRequest);
            catch (Exception e)
                Console.WriteLine(e.Message);
        }
        // Helper function that constructs ETags.
        static List<PartETag> GetETags(List<CopyPartResponse> responses)
            List<PartETag> etags = new List<PartETag>();
            foreach (CopyPartResponse response in responses)
                etags.Add(new PartETag(response.PartNumber, response.ETag));
            return etags;
        }
    }
```

Copy Object Using the REST Multipart Upload API

The following sections in the *Amazon Simple Storage Service API Reference* describe the REST API for multipart upload. For copying an existing object you use the Upload Part (Copy) API and specify the source object by adding the x-amz-copy-source request header in your request.

- Initiate Multipart Upload
- Upload Part
- Upload Part (Copy)
- · Complete Multipart Upload
- · Abort Multipart Upload
- List Parts
- · List Multipart Uploads

You can use these APIs to make your own REST requests, or you can use one the SDKs we provide. For more information about the SDKs, see API Support for Multipart Upload (p. 108).

Listing Object Keys

Keys can be listed by prefix. By choosing a common prefix for the names of related keys and marking these keys with a special character that delimits hierarchy, you can use the list operation to select and browse keys hierarchically. This is similar to how files are stored in directories within a file system.

Amazon S3 exposes a list operation that lets you enumerate the keys contained in a bucket. Keys are selected for listing by bucket and prefix. For example, consider a bucket named "dictionary" that contains a key for every English word. You might make a call to list all the keys in that bucket that start with the letter "q". List results are always returned in lexicographic (alphabetical) order.

Both the SOAP and REST list operations return an XML document that contains the names of matching keys and information about the object identified by each key.

You can iterate through large collections of keys by making multiple, paginated, list requests. For example, an initial list request against the dictionary bucket might retrieve only information about the keys "quack" through "quartermaster". But a subsequent request would retrieve "quarters" through "quince", and so on.

For instructions on how to correctly handle large list result sets, see Iterating Through Multi-Page Results (p. 194).

Groups of keys that share a prefix terminated by a special delimiter can be rolled up by that common prefix for the purposes of listing. This enables applications to organize and browse their keys hierarchically, much like how you would organize your files into directories in a file system. For example, to extend the dictionary bucket to contain more than just English words, you might form keys by prefixing each word with its language and a delimiter, such as "French/logical". Using this naming scheme and the hierarchical listing feature, you could retrieve a list of only French words. You could also browse the top-level list of available languages without having to iterate through all the lexicographically intervening keys.

For more information on this aspect of listing, see Listing Keys Hierarchically Using Prefix and Delimiter (p. 194).

List Implementation Efficiency

List performance is not substantially affected by the total number of keys in your bucket, nor by the presence or absence of the prefix, marker, maxkeys, or delimiter arguments.

Iterating Through Multi-Page Results

As buckets can contain a virtually unlimited number of keys, the complete results of a list query can be extremely large. To manage large result sets, Amazon S3 uses pagination to split them into multiple responses. Each list keys response returns a page of up to 1,000 keys with an indicator indicating if the response is truncated. You send a series of list keys requests until you have received all the keys.

Listing Keys Hierarchically Using Prefix and Delimiter

The prefix and delimiter parameters limit the kind of results returned by a list operation. Prefix limits results to only those keys that begin with the specified prefix, and delimiter causes list to roll up all keys that share a common prefix into a single summary list result.

The purpose of the prefix and delimiter parameters is to help you organize and then browse your keys hierarchically. To do this, first pick a delimiter for your bucket, such as slash (/), that doesn't occur in any of your anticipated key names. Next, construct your key names by concatenating all containing levels of the hierarchy, separating each level with the delimiter.

For example, if you were storing information about cities, you might naturally organize them by continent, then by country, then by province or state. Because these names don't usually contain punctuation, you might select slash (/) as the delimiter. The following examples use a slash (/) delimiter.

- Europe/France/Aquitaine/Bordeaux
- North America/Canada/Quebec/Montreal
- North America/USA/California/San Francisco
- North America/USA/Washington/Seattle

and so on.

If you stored data for every city in the world in this manner, it would become awkward to manage a flat key namespace. By using <code>Prefix</code> and <code>Delimiter</code> with the list operation, you can use the hierarchy you've created to list your data. For example, to list all the states in USA, set <code>Delimiter='/'</code> and <code>Prefix='/North</code> America/USA/'. To list all the provinces in Canada for which you have data, set <code>Delimiter='/'</code> and <code>Prefix='North</code> America/Canada/'.

A list request with a delimiter lets you browse your hierarchy at just one level, skipping over and summarizing the (possibly millions of) keys nested at deeper levels. For example, assume you have a bucket (ExampleBucket) the following keys.

```
sample.jpg
photos/2006/January/sample.jpg
photos/2006/February/sample2.jpg
photos/2006/February/sample3.jpg
photos/2006/February/sample4.jpg
```

The sample bucket has only the <code>sample.jpg</code> object at the root level. To list only the root level objects in the bucket you send a GET request on the bucket with "/" delimiter character. In response, Amazon S3 returns the the <code>sample.jpg</code> object key because it does not contain the "/" delimiter character. All other keys contain the delimiter character. Amazon S3 groups these keys and return a single

CommonPrefixes element with prefix value photos/ that is a substring from the beginning of these keys to the first occurrence of the specified delimiter.

```
<ListBucketResult xmlns="http://s3.amazonaws.com/doc/2006-03-01/">
 <Name>ExampleBucket</Name>
 <Prefix></Prefix>
 <Marker></Marker>
 <MaxKeys>1000</MaxKeys>
 <Delimiter>/</Delimiter>
 <IsTruncated>false</IsTruncated>
 <Contents>
   <Key>sample.jpg</Key>
   <LastModified>2011-07-24T19:39:30.000Z</LastModified>
   <ETaq>&quot;d1a7fb5eab1c16cb4f7cf341cf188c3d&quot;</ETaq>
   <Size>6</Size>
   <Owner>
     <ID>852b113e7a2f25102679df27bb0ae12b3f85be6f290b936c4393484be31aaaaa</ID>
     <DisplayName>mohanataws/DisplayName>
   </Owner>
   <StorageClass>STANDARD</StorageClass>
 </Contents>
 <CommonPrefixes>
   <Prefix>photos/</Prefix>
 </CommonPrefixes>
</ListBucketResult>
```

Listing Keys Using the AWS SDK for Java

The following tasks guide you through using the Java classes to list object keys in a bucket. You have many options for listing the objects in your bucket. Note that for buckets with large number of objects you might get truncated results when listing the objects. You should check to see if the returned object listing is truncated, and use the AmazonS3.listNextBatchOfObjects operation to retrieve additional results.

Listing Object Keys

1	Create an instance of the AmazonS3Client class by providing your AWS credentials.
2	Execute one of the AmazonS3Client.listObjects methods. You need to provide the request information, such as the bucket name, and the optional key prefix. You provide this information by creating an instance of the ListObjectsRequest class. For listing objects, Amazon S3 returns up to 1,000 keys in the response. If you have more than 1,000 keys in your bucket, the response will be truncated. You should always check for if the response is truncated.

The following Java code sample demonstrates the preceding tasks.

Amazon Simple Storage Service Developer Guide Listing Keys Using the AWS SDK for Java

The following Java code example list object keys in an Amazon S3 bucket. For instructions on how to create and test a working sample, see Testing the Java Code Examples (p. 327)

```
import java.io.IOException;
import com.amazonaws.AmazonClientException;
import com.amazonaws.AmazonServiceException;
import com.amazonaws.auth.PropertiesCredentials;
import com.amazonaws.services.s3.AmazonS3;
import com.amazonaws.services.s3.AmazonS3Client;
import com.amazonaws.services.s3.model.ListObjectsRequest;
import com.amazonaws.services.s3.model.ObjectListing;
import com.amazonaws.services.s3.model.S30bjectSummary;
public class S3Sample {
private static String bucketName = "*** Provide bucket name ***";
public static void main(String[] args) throws IOException {
       AmazonS3 s3client = new AmazonS3Client(new PropertiesCredentials(
                S3Sample.class.getResourceAsStream(
                  "AwsCredentials.properties")));
        try {
             System.out.println("Listing objects");
           ObjectListing objectListing = s3client.listObjects(new
             ListObjectsRequest()
                    .withBucketName(bucketName)
                    .withPrefix("m")
                    );
           do {
             for (S3ObjectSummary objectSummary :
             objectListing.getObjectSummaries()) {
                 System.out.println(" - " + objectSummary.getKey() + " " +
                                    "(size = " + objectSummary.getSize() +
                                    ")");
            objectListing = s3client.listNextBatchOfObjects(objectListing);
            } while (objectListing.isTruncated());
         } catch (AmazonServiceException ase) {
           System.out.println("Caught an AmazonServiceException, " +
              "which means your request made it " +
                    "to Amazon S3, but was rejected with an error response " +
                    "for some reason.");
           System.out.println("Error Message:
                                                  " + ase.getMessage());
           System.out.println("HTTP Status Code: " + ase.getStatusCode());
           System.out.println("AWS Error Code: " + ase.getErrorCode());
           System.out.println("Error Type:
                                                  " + ase.getErrorType());
                                                  " + ase.getRequestId());
           System.out.println("Request ID:
        } catch (AmazonClientException ace) {
           System.out.println("Caught an AmazonClientException, " +
              "which means the client encountered " +
                    "an internal error while trying to communicate" +
                    " with S3, " +
```

```
"such as not being able to access the network.");
System.out.println("Error Message: " + ace.getMessage());
}
}
```

Listing Keys Using the AWS SDK for .NET

The following tasks guide you through using the .NET classes to list object keys in a bucket.

Listing Object Keys

1	Create an instance of the AmazonS3 class by providing your AWS credentials.			
2	Execute one of the AmazonS3.ListObjects. You need to provide the bucket name to list the keys. You can also specify optional information, such as retrieving keys starting with a specific prefix, and limiting result set to a specific number of keys. By default, the result set returns up to 1,000 keys. You provide this information by creating an instance of the ListObjectsRequest class.			
3	Process the ListObjectResponse by iterating over the ListObjectResponse.S30bjects collection. You should check to see if the result was truncated. If yes, you send a request for the next set of keys by setting the ListObjectRequest.Marker value to the NextMarker value received in the previous response.			

The following C# code sample demonstrates the preceding tasks.

```
static AmazonS3 client;
client = Amazon.AWSClientFactory.CreateAmazonS3Client(
                    accessKeyID, secretAccessKeyID);
ListObjectsRequest request = new ListObjectsRequest();
request = new ListObjectsRequest();
request.BucketName = bucketName;
request.WithPrefix("m");
request.MaxKeys = 2;
do
  ListObjectsResponse response = client.ListObjects(request);
   // Process response.
   // If response is truncated, set the marker to get the next
   // set of keys.
  if (response.IsTruncated)
        request.Marker = response.NextMarker;
   }
        else
        request = null;
```

Amazon Simple Storage Service Developer Guide Listing Keys Using the AWS SDK for .NET

```
} while (request != null);
```

The following C# code example lists keys in the specified bucket. The example illustrates the use of AmazonS3.ListObjects method. It also illustrates how you can specify options to list keys, such as listing keys with a specific prefix, listing keys that start after a specific marker, and listing only a specific number of keys. For instructions on how to create and test a working sample, see Testing the .NET Code Examples (p. 328)

```
using System;
using System.Configuration;
using System.Collections.Specialized;
using Amazon.S3;
using Amazon.S3.Model;
namespace s3.amazon.com.docsamples.listingkeys
    class S3Sample
        static string bucketName = "*** Provide bucket name ***";
        static AmazonS3 client;
        public static void Main(string[] args)
            if (checkRequiredFields())
                NameValueCollection appConfig =
                    ConfigurationManager.AppSettings;
                string accessKeyID = appConfig["AWSAccessKey"];
                string secretAccessKeyID = appConfig["AWSSecretKey"];
                using (client = Amazon.AWSClientFactory.CreateAmazonS3Client(
                    accessKeyID, secretAccessKeyID))
                   Console.WriteLine("Listing objects stored in a bucket");
                    ListingObjects();
                }
            }
            Console.WriteLine("Press any key to continue...");
            Console.ReadKey();
        }
        static void ListingObjects()
            try
                ListObjectsRequest request = new ListObjectsRequest();
                request = new ListObjectsRequest();
                request.BucketName = bucketName;
                request.WithPrefix("m");
                request.MaxKeys = 2;
               do
                   ListObjectsResponse response = client.ListObjects(request);
```

```
// Process response.
           foreach (S3Object entry in response.S3Objects)
               Console.WriteLine("key = \{0\} size = \{1\}",
                   entry.Key, entry.Size);
           // If response is truncated, set the marker to get the next
           // set of keys.
           if (response.IsTruncated)
               request.Marker = response.NextMarker;
           }
           else
               request = null;
       } while (request != null);
   catch (AmazonS3Exception amazonS3Exception)
        if (amazonS3Exception.ErrorCode != null &&
            (amazonS3Exception.ErrorCode.Equals("InvalidAccessKeyId")
            amazonS3Exception.ErrorCode.Equals("InvalidSecurity")))
            Console.WriteLine("Check the provided AWS Credentials.");
            Console.WriteLine(
            "To sign up for service, go to http://aws.amazon.com/s3");
        }
        else
            Console.WriteLine(
             "Error occurred. Message: '{0}' when listing objects",
             amazonS3Exception.Message);
    }
static bool checkRequiredFields()
   NameValueCollection appConfig = ConfigurationManager.AppSettings;
   if (string.IsNullOrEmpty(appConfig["AWSAccessKey"]))
        Console.WriteLine(
            "AWSAccessKey was not set in the App.config file.");
        return false;
   if (string.IsNullOrEmpty(appConfig["AWSSecretKey"]))
        Console.WriteLine(
            "AWSSecretKey was not set in the App.config file.");
        return false;
   if (string.IsNullOrEmpty(bucketName))
```

Amazon Simple Storage Service Developer Guide Listing Keys Using the AWS SDK for PHP

Listing Keys Using the AWS SDK for PHP

When enumerating objects in a bucket you have option of using the low-level list_objects() method or the high-level get_object_list() method.

The low-level list_objects() method maps to the underlying Amazon S3 REST API. Each list_objects() request returns you a page of up to 1,000 object keys. If you have more than 1,000 objects in the bucket, your response will be truncated. You will need to send another list_objects() request to fetch the next set of 1,000 keys. This method returns the entire Amazon S3 response. For example, in addition to key names, the response includes object metadata such as content size and the last modified date.

The high-level <code>get_object_list()</code> method provides higher level of abstraction which simplifies your coding efforts. For example, you don't need to worry if the response is truncated or not. The method returns all the keys from the specified bucket. Internally, this API makes all the necessary calls to ensure all the keys are retrieved. However, the API returns only object keys names in an array. You use this high-level API is to enumerate object keys from a specific bucket.

The following tasks guide you through using the PHP classes to list object keys in a bucket.

Listing Object Keys

1	Create an instance of the AmazonS3 class by providing your AWS credentials.			
2	Execute the high-level AmazonS3::get_object_list() or the low-level AmazonS3::list_objects() method by providing the bucket name as input.			

The following PHP code sample demonstrates the preceding tasks.

```
// Instantiate the class.
$s3 = new AmazonS3();
// Use the high-level API.
$response = $s3->get_object_list($bucket);

// Or, use the low-level API().
$response = $s3->list_objects($bucket);
// Process response.
```

The following PHP example lists keys from a specified bucket. The example illustrates the use of the both the high-level <code>get_object_list()</code> method and the low-level <code>list_objects()</code> method to enumerate objects in a bucket. The example also illustrates processing the response returned by these methods.

```
<?php
require_once '../aws-sdk-for-php/sdk.class.php';
header('Content-Type: text/plain; charset=utf-8');
$bucket = *** Provide bucket name ***';
// Instantiate the class.
$s3 = new AmazonS3();
     1. High-level API returns all keys. However only key names are returned.
$response = $s3->get_object_list($bucket);
// Success?
print_r(gettype($response) === 'array');
if($response)
   echo "Keys retrieved!" . PHP_EOL;
 foreach ($response as $key)
    {
        echo $key . PHP_EOL;
}
    2. Low-level API. Response returns up to 1,000 keys.
       However, response has more information than just key names.
* /
$response = $s3->list_objects($bucket);
foreach ($response->body->Contents as $content)
   echo (string) $content->Key . ' - ' .
        $s3->util->size_readable((string) $content->Size) . ' - ' .
        date('j M Y', strtotime((string) $content->LastModified)) . PHP_EOL;
```

Listing Keys Using the REST API

You can use the AWS SDK to retrieve an object. However, if your application requires it, you can send REST requests directly. You can send a GET request to retrieve an object or portion of the object. For more information, go to Get Object.

Related Resources

Using the AWS SDKs and Explorers (p. 325)

Access Control

Topics

- Using IAM Policies (p. 205)
- Using Bucket Policies (p. 216)
- Using ACLs (p. 228)
- Using ACLs and Bucket Policies Together (p. 244)
- Using Query String Authentication (p. 245)

Amazon S3 enables you to manage access to objects and buckets using access control lists (ACLs) and bucket policies. You can use them independently or together. This section describes both.

An ACL is a list of grants. A grant consists of one grantee and one permission to access Amazon S3 resources (buckets and objects). ACLs only grant permissions; they do not deny them. ACLs can contain the following grantee types:

- · Specific AWS accounts
- · All AWS accounts
- · Any anonymous request

Bucket policies provide access control management at the bucket level for both a bucket and the objects in it. Bucket policies are a collection of JSON statements written in the *access policy language*. The policies provide a fine granularity of access control for Amazon S3 resources. The policies also allow you to set permissions for a large number of objects with one statement.

Using IAM Policies

Topics

- IAM and Bucket Policies Together (p. 205)
- Permissions for Resource Creator (p. 208)
- Amazon S3 ARNs (p. 208)
- Amazon S3 Actions (p. 208)
- Amazon S3 Policy Keys (p. 209)
- Example Policies for Amazon S3 (p. 214)

AWS Identity and Access Management (IAM) enables you to create multiple users within your AWS account, assign them security credentials, and manage their permissions. You manage user permissions via IAM policies. These policies are attached to the users, enabling centralized control of permissions for users under your AWS account.

Amazon S3 supports resource-based permissions on objects and buckets using access control list (ACL) and bucket policies. The ACLs and bucket policies are attached to buckets and objects defining which AWS accounts (or other groups of actors) have access and the type of access.

You can use both of these in conjunction with IAM user policies to control access to your Amazon S3 resources. The following table summarizes similarities and differences between ACLs, bucket policies, and IAM policies.

Type of Access Control	AWS Account-Level Control?	User-Level Control?	Format
ACLs	Yes	No	Special XML-based format defined by Amazon S3
Bucket policies	Yes	Yes	Access policy language
IAM policies	No	Yes	Access policy language

With ACLs, you can only grant other AWS accounts access to your Amazon S3 resources. With IAM policies, you can only grant users within your own AWS account permission to your Amazon S3 resources. With bucket policies, you can do both.

This section describes how IAM works with bucket policies and ACLs.


IAM and Bucket Policies Together

When someone sends a request to use your AWS account's Amazon S3 resources, we evaluate all applicable ACLs, bucket policies, and IAM policies together to determine whether to give the requester access.

Although you can still use ACLs to grant permission, this section focuses on how to use IAM policies and bucket policies to give *users in your AWS account* permissions to access your Amazon S3 resources. You can use bucket policies, IAM policies, or both. For the most part, you can achieve the same results with either. For example, the following diagram shows an IAM policy and a bucket policy that are equivalent. The IAM policy (on the left) allows the Amazon S3 PutObject action for the bucket called bucket_xyz in your AWS account, and it's attached to the users Bob and Susan (which means Bob and Susan have the permissions stated in the policy).

Amazon Simple Storage Service Developer Guide IAM and Bucket Policies Together

The bucket policy (on the right) is attached to bucket_xyz. As with the IAM policy, the bucket policy gives Bob and Susan permission to access PutObject on bucket xyz.






Note

The preceding example shows simple policies with no conditions. You could specify a particular condition in either policy and get the same result.

IAM policies lets you manage access to your Amazon S3 resources based on user; whereas bucket policies let you manage access based on the specific resources. The following examples further illustrate how the two policy systems work together.


In this example, Bob has both an IAM policy and a bucket policy that apply to him. The IAM policy gives him permission to use PutObject on bucket_xyz, whereas the bucket policy gives him permission to use ListBucket on that same bucket. The following diagram illustrates the concept.



If Bob were to send a request to put an object into bucket_xyz, the IAM policy would allow the action. If Bob were to send a request to list the objects in bucket_xyz, the bucket policy would allow the action.

Example 2

In this example, we build on the previous example (where Bob has two policies that apply to him). Let's say that Bob abuses his access to bucket_xyz, so you want to remove his entire access to that bucket. The easiest thing to do is add a policy that denies him access to all actions on the bucket. This third policy overrides the other two, because an explicit deny always overrides an allow (for more information about policy evaluation logic, see Evaluation Logic (p. 338)). The following diagram illustrates the concept.



Amazon Simple Storage Service Developer Guide Permissions for Resource Creator

Alternatively, you could add an additional statement to the bucket policy that denies Bob any type of access to the bucket. It would have the same effect as adding a IAM policy that denies him access to the bucket.

For examples of policies that cover Amazon S3 actions and resources, see Example Policies for Amazon S3 (p. 214). For more information about writing S3 policies, go to the Amazon Simple Storage Service Developer Guide.

Permissions for Resource Creator

Amazon S3 by default gives the AWS account that created the bucket or object full permissions on that resource. However, if a user (not the AWS account) creates a bucket or object, that user doesn't by default have permission to perform other actions on that resource. The user must be granted the additional permissions in an IAM policy.

Amazon S3 ARNs

For Amazon S3, the resources you can specify in a policy are buckets and objects. The Amazon Resource Name (ARN) follows this format:

```
arn:aws:s3:::bucket_name/key_name
```

where arn:aws:s3:::bucket_name refers only to the bucket, and the entire string arn:aws:s3:::bucket_name/key_name refers to the object.

For example:

```
arn:aws:s3:::example_bucket/developers/design_info.doc
```

The Region and AWS Account ID portions of the ARN must be empty because bucket names are global.

Amazon S3 Actions

The Amazon S3 actions that you can specify in a policy are divided into groups based on the type of resource.

Actions Related to Objects

- s3:GetObject (covers REST GET Object, REST HEAD Object, REST GET Object torrent, SOAP GetObject, and SOAP GetObjectExtended)
- s3:GetObjectVersion (covers REST GET Object, REST HEAD Object, REST GET Object torrent, SOAP GetObject, and SOAP GetObjectExtended)
- s3:PutObject (covers the REST PUT Object, REST POST Object, REST Initiate Multipart Upload, REST Upload Part, REST Complete Multipart Upload, SOAP PutObject, and SOAP PutObjectInline)
- s3:GetObjectAcl
- s3:GetObjectVersionAcl
- s3:PutObjectAcl
- s3:PutObjectVersionAcl
- s3:DeleteObject
- s3:DeleteObjectVersion
- s3:ListMultipartUploadParts

• s3:AbortMultipartUpload

Actions Related to Buckets

- s3:CreateBucket
- s3:DeleteBucket
- s3:ListBucket
- s3:ListBucketVersions
- s3:ListAllMyBuckets (covers REST GET Service and SOAP ListAllMyBuckets)
- s3:ListBucketMultipartUploads

Actions Related to Bucket Sub-Resources

- s3:GetBucketAcl
- s3:PutBucketAcl
- s3:GetBucketVersioning
- s3:PutBucketVersioning
- s3:GetBucketRequesterPays
- s3:PutBucketRequesterPays
- s3:GetBucketLocation
- s3:GetBucketPolicy
- s3:PutBucketPolicy
- s3:GetBucketNotification
- s3:PutBucketNotification
- s3:GetBucketLogging
- s3:PutBucketLogging

Amazon S3 Policy Keys

Policy keys let you restrict access to resources based on information other than just the API action being requested. They let you restrict access based on contextual information about the request, such as the IP address of the requester, the time and date of the request, etc. Amazon S3 has a rich integration with IAM that lets you restrict access based on a wide variety of contextual information about the request. For example, you can restrict access based on values of general HTTP headers or Amazon S3-specific headers in the request. This section lists the policy keys available for you to use with policies that restrict access to your AWS account's Amazon S3 resources. For more information about policy keys, see Condition (p. 345).

Amazon S3 implements the AWS-wide policy keys in the following table.

Available Keys

AWS provides a set of common keys supported by all AWS products that adopt the access policy language for access control. These keys are:

- aws:CurrentTime—Key to use with date conditions to restrict access based on request time. For date/time conditions (see Date Conditions (p. 349))
- aws:SecureTransport—Boolean representing whether the request was sent using SSL (see Boolean Conditions (p. 349))
- aws:SourceIp-The requester's IP address, for use with IP address conditions (see IP Address (p. 349))

Amazon Simple Storage Service Developer Guide Amazon S3 Policy Keys

- aws:UserAgent-Information about the requester's client application, for use with string conditions (see String Conditions (p. 348))
- aws:EpochTime-Number of seconds since epoch.
- aws:Referer-Same as the HTTP referer field.

The key names are case insensitive. For example, aws: CurrentTime is equivalent to AWS: currenttime.



Note

If you use aws: SourceIp, and the request comes from an Amazon EC2 instance, we evaluate the instance's public IP address to determine if access is allowed.

Each AWS service that uses the access policy language might also provide service-specific keys. For a list of service-specific keys you can use, see Special Information for Amazon S3 Policies (p. 352).

Amazon S3 also has action-specific policy keys. They're grouped by resource type and applicable action in the following tables. Some policy keys are applicable to more than one resource type or action.



Important

IAM cannot evaluate a policy for validity within Amazon S3. If you specify an invalid key/action combination in the policy, IAM doesn't throw an error when you upload the policy to IAM. Also, you will not receive an error message from Amazon S3. Amazon S3 can determine only that the policy doesn't apply because it cannot fulfill the conditions. However, if you use a policy condition in an unexpected way (for example, you use a string field as a numeric comparison), Amazon S3 will throw an exception on the request and access will be denied.

Unless otherwise noted, each key is for use with the access policy language's string conditions (for more information, see String Conditions (p. 348)).

Object Keys in Amazon S3 Policies

The following list shows the keys related to objects that can be in Amazon S3 policies.

Action	Applicable Keys	Description	
s3:PutObject	s3:x-amz-acl	The Amazon S3 canned ACL that is applied to the object. A canned ACL represents a predefined permission that can be applied to the object being PUT to Amazon S3. Valid values: private public-read public-read-write authenticated-read bucket-owner-read bucket-owner-full-control log-delivery-write. Example value: public-read	
	s3:x-amz-copy-source	The header that specifies the name of the source bucket and key name of the source object, separated by a slash (/). Used when copying an object. Example value: /bucketname/keyname	
	s3:x-amz-metadata-di rective	The header that specifies whether the metadata is copied from the source object or replaced with metadata provided in the request. If copied, the metadata, except for the version ID, remains unchanged. Otherwise, all original metadata is replaced by the metadata you specify. Used when copying an object. Valid values: COPY REPLACE. The default is COPY. Example value: REPLACE	
s3:PutObjectAcl	s3:x-amz-acl	The Amazon S3 canned ACL that is applied to the object. A canned ACL represents a predefined permission that can be applied to the object being PUT to Amazon S3. Valid values: private public-read public-read-write authenticated-read bucket-owner-read bucket-owner-full-control log-delivery-write. Example value: public-read	

Amazon Simple Storage Service Developer Guide Amazon S3 Policy Keys

Action	Applicable Keys	Description
s3:GetObjectVersion	s3:VersionId	The version ID of the object being retrieved. Example value: Upfdndhfd8438MNFDN93 jdnJFkdmqnh893
s3:GetObjectVersionA	s3:VersionId	The version ID of the object ACL being retrieved. Example value: Upfdndhfd8438MNFDN93 jdnJFkdmqnh893
s3:PutObjectVersionA	s3:VersionId	The version ID of the object ACL being PUT. Example value: Upfdndhfd8438MNFDN93 jdnJFkdmqnh893
	s3:x-amz-acl	The Amazon S3 canned ACL that is applied to the object. A canned ACL represents a predefined permission that can be applied to the object being PUT to Amazon S3. Valid values: private public-read public-read-write authenticated-read bucket-owner-read bucket-owner-full-control log-delivery-write. Example value: public-read
s3:DeleteObjectVersi on	s3:VersionId	The version ID of the object being deleted. Example value: Upfdndhfd8438MNFDN93 jdnJFkdmqnh893

Bucket Keys in Amazon S3 Policies

The following table shows the keys related to buckets that can be in Amazon S3 policies.

Action	Applicable Keys	Description	
s3:CreateBucket	s3:x-amz-acl	The Amazon S3 canned ACL that is applied to the bucket. A canned ACL represents a predefined permission that can be applied to the bucket being created. Valid values: private public-read public-read-write authenticated-read bucket-owner-read bucket-owner-full-control log-delivery-write.	
		Example value: public-read	
	s3:LocationConstraint	Specifies the Region where the bucket will be created. Valid values are us-west-1 (for Northern California) or EU (for Ireland). Do not specify a value for US Standard. Example value: us-west-1	
s3:ListBucket	s3:prefix	Limits the response to objects that begin with the specified prefix. Use this to allow or deny access to objects that begin with the prefix. Example value: home	
	s3:delimiter	The character you use to group objects. Example value: /	
	s3:max-keys	The number of objects to return from the call. The maximum allowed value (and default) is 1000. For use with access policy language numeric conditions (for more information, see Numeric Conditions (p. 348)). Example value: 100	

Amazon Simple Storage Service Developer Guide Example Policies for Amazon S3

Action	Applicable Keys	Description
s3:ListBucketVersion s	s3:prefix	Header that lets you limit the response to include only keys that begin with the specified prefix. Example value: home
	s3:delimiter	The character you use to group objects. Example value: /
	s3:max-keys	The number of objects to return from the call. The maximum allowed value (and default) is 1000. For use with access policy language numeric conditions (for more information,
		see Numeric Conditions (p. 348)). Example value: 100
s3:PutBucketAcl	s3:x-amz-acl	The Amazon S3 canned ACL that is applied to the bucket. A canned ACL represents a predefined permission that can be applied to the bucket being created.
		Valid values: private public-read public-read-write authenticated-read
		<pre>bucket-owner-read bucket-owner-full-control log-delivery-write.</pre>
		Example value: public-read

Example Policies for Amazon S3

This section shows several simple IAM policies for controlling user access to Amazon S3.



Note

In the future, Amazon S3 might add new actions that should logically be included in one of the following policies, based on the policy's stated goals.

Example 1: Allow each user to have a home directory in Amazon S3

In this example, we create a policy that we'll attach to the user named Bob. The policy gives Bob access to the following home directory in Amazon S3: my_corporate_bucket/home/bob. Bob is allowed to access only the specific Amazon S3 actions shown in the policy, and only with the objects in his home directory.

```
{
    "Statement":[{
        "Effect":"Allow",
        "Action":["s3:PutObject","s3:GetObjectVersion",
        "s3:DeleteObject","s3:DeleteObjectVersion"],
        "Resource":"arn:aws:s3:::my_corporate_bucket/home/bob/*"
    }
}
```

Example 2: Allow a user to list only the objects in his or her home directory in the corporate bucket

This example builds on the previous example that gives Bob a home directory. To give Bob the ability to list the objects in his home directory, he needs access to ListBucket. However, we want the results to include only objects in his home directory, and not everything in the bucket. To restrict his access that way, we use the policy condition key called s3:prefix with the value set to home/bob/*. This means that only objects with a prefix home/bob/* will be returned in the ListBucket response.

Example 3: Allow a group to have a shared directory in Amazon S3

In this example, we create a policy that gives the group access to the following directory in Amazon S3: my_corporate_bucket/share/marketing. The group is allowed to access only the specific Amazon S3 actions shown in the policy, and only with the objects in the specific directory.

Example 4: Allow all your users to read objects in a portion of the corporate bucket

In this example we create a group called *AllUsers* and put all the AWS account's users in the group. We then attach a policy that gives the group access to <code>GetObject</code> and <code>GetObjectVersion</code>, but only for objects in the my_corporate_bucket/readonly directory.

```
{
   "Statement":[{
        "Effect":"Allow",
        "Action":["s3:GetObject","s3:GetObjectVersion"],
        "Resource":"arn:aws:s3:::my_corporate_bucket/readonly/*"
     }
}
```

Example 5: Allow a partner to drop files into a specific portion of the corporate bucket

In this example, we create a group called WidgetCo that represents the partner company, then create a user for the specific person (or application) at the partner company who needs access, and then put the user in the group.

We then attach a policy that gives the group PutObject access to the following directory in the corporate bucket: my_corporate bucket/uploads/widgetco.

We also want to prevent the WidgetCo group from doing anything else with the bucket, so we add a statement that denies permission to any Amazon S3 actions except PutObject on any Amazon S3 resource in the AWS account. This is only necessary if there's a broad policy in use elsewhere in your AWS account that gives users wide access to Amazon S3.

```
{
    "Statement":[{
        "Effect":"Allow",
        "Action":"s3:PutObject",
        "Resource":"arn:aws:s3:::my_corporate_bucket/uploads/widgetco/*"
},
    "Effect":"Deny",
        "NotAction":"s3:PutObject",
        "Resource":["arn:aws:s3:::my_corporate_bucket/uploads/widgetco/*"]
},
    {
        "Effect":"Deny",
        "Action":"s3:*",
        "NotResource": "arn:aws:s3:::my_corporate_bucket/uploads/widgetco/*"
}]
}
```

Using Bucket Policies

Topics

- Writing Bucket Policies (p. 217)
- Setting Bucket Policies on a Bucket (p. 217)
- Returning the Bucket Policies on a Bucket (p. 218)
- Deleting Bucket Policies on a Bucket (p. 218)

Amazon Simple Storage Service Developer Guide Writing Bucket Policies

- Example Cases for Amazon S3 Bucket Policies (p. 218)
- How to Use Resources, Principals, Operations, and Conditions in Bucket Policies (p. 222)

The following sections explain how to set and manage bucket policies on Amazon S3 resources.

Writing Bucket Policies

Bucket policies define access rights for Amazon S3 resources. Only a bucket owner can write bucket policies. A bucket owner can write a bucket policy to:

- · Allow/deny bucket-level permissions.
- Deny permission on any objects in the bucket. Because the bucket owner is fiscally responsible for the bucket, the owner can write a bucket policy to deny permissions on any objects in a bucket.
- Grant permission on objects in the bucket only if the bucket owner is the object owner. For objects owned by other accounts the object owner must manage permissions using ACLs.

The policy itself is written in JSON and uses the access policy language. To learn about the details of the access policy language and how to write a bucket policy, see The access policy language (p. 332).

AWS Policy Generator Tool

You can use the AWS Policy Generator tool to create a bucket policy for your Amazon S3 bucket. You can then use the generated document to set your bucket policy using the Amazon S3 console, a number of third party tools or via your application. To use the policy generation tool, go to AWS Policy Generator.

Setting Bucket Policies on a Bucket

To set a policy on a bucket, you use the PUT Bucket operation on the policy sub-resource and you include the bucket policy in the body of the request. The following request, for example, allows two users (1-22-333-4444, 3-55-678-9100) access execute a GET request (s3:GetObject*) for objects in mybucket (arn:aws:s3:::mybucket/*",):

```
PUT /?policy HTTP/1.1
Host: bucket.s3.amazonaws.com
Date: Tue, 04 Apr 2010 20:34:56 GMT
Authorization: AWS VGhpcyBSAMPLEBieSBlbHZpbmc=
"Version": "2008-10-17",
"Id": "aaaa-bbbb-cccc-dddd",
"Statement" : [
    {
        "Effect": "Allow",
        "Sid":"1",
        "Principal" : {
            "AWS":["1-22-333-4444","3-55-678-9100"]
        "Action":["s3:GetObject*"],
        "Resource": "arn:aws:s3:::mybucket/*",
    }
 ]
```



Note

The Resource value must include the bucket name.

To attach a policy to a bucket, you must be the bucket owner or someone authorized by the bucket owner to set a policy on the bucket by being granted <code>PutPolicy</code> permissions. The bucket owner by default has permissions to attach bucket policies to their buckets using <code>PUT Bucket policy</code>. If the bucket already has a policy, the one in this request completely replaces it

For more information, go to PUT Bucket policy in the Amazon S3 API Reference.

Returning the Bucket Policies on a Bucket

To return the bucket policy on a specified bucket, use the GET Bucket operation with the policy sub-resource. The following request returns the bucket policy for the bucket, mybucket.s3.amazonaws.com:

```
GET ?policy HTTP/1.1

Host: mybucket.s3.amazonaws.com

Date: Wed, 28 Oct 2009 22:32:00 GMT

Authorization: AWS 02236Q3V0WHVSRSAMPLEX5sCYVf1bNRuU=
```

The bucket owner by default has permissions to retrieve bucket policies using GET Bucket policy.

For more information, go to GET Bucket policy in the Amazon S3 API Reference.

Deleting Bucket Policies on a Bucket

To delete a policy associated with a bucket, use the DELETE Bucket operation with the policy sub-resource. The following request deletes the bucket policy associated with mybucket:

```
DELETE /?policy HTTP/1.1
Host: mybucket.s3.amazonaws.com
Date: Tue, 04 Apr 2010 20:34:56 GMT
Authorization: AWS VGhpcyBSAMPLEeSBlbHZpbmc=
```

To use the delete operation, you must have <code>DeletePolicy</code> permissions on the specified bucket and be the bucket owner. The bucket owner by default has permissions to delete bucket policies.

For more information, go to DELETE Bucket policy in the Amazon S3 API Reference.

Example Cases for Amazon S3 Bucket Policies

This section gives a few examples of typical use cases for bucket policies.



Note

You can use the AWS Policy Generator tool to create a bucket policy for your Amazon S3 bucket. You can then use the generated document to set your bucket policy using the Amazon S3 console, a number of third party tools or via your application. To use the policy generation tool, go to AWS Policy Generator.

Granting Permissions to Multiple Accounts with Added Restrictions

The following example policy grants PutObject, and PutObjectAcl permissions to multiple accounts and requires that the public-read canned acl is included.

Example

```
"Version": "2008-10-17",
  "Statement":[{
 "Sid": "AddCannedAcl",
        "Effect": "Allow",
   "Principal": {
            "AWS":
["arn:aws:iam::778695189650:root", "arn:aws:iam::178784293420:root"]
   "Action":["s3:PutObject","s3:PutObjectAcl"
      ],
      "Resource":["arn:aws:s3:::bucket/*"
      ],
      "Condition":{
        "StringEquals":{
          "s3:x-amz-acl":["public-read"]
    }
 1
```

Granting Permission to an Anonymous User

The following example policy grants permissions to anonymous users.

Example

Restricting Access to Specific IP Addresses

This statement grants permissions to any user to perform any S3 action on objects in the specified bucket. However, the request must originate from the range of IP addresses specified in the condition. The

condition in this statement identifies 192.168.143.* range of allowed IP addresses with one exception, 192.168.143.188.

Note that the IPAddress and NotIpAddress values specified in the condition uses CIDR notation described in RFC 2632. For more information, go to http://www.rfc-editor.org/rfc/rfc4632.txt.

Example

```
"Version": "2008-10-17",
"Id": "S3PolicyId1",
"Statement": [
        "Sid": "IPAllow",
        "Effect": "Allow",
        "Principal": {
            "AWS": "*"
        "Action": "s3:*",
        "Resource": "arn:aws:s3:::bucket/*",
        "Condition" : {
            "IpAddress" : {
                "aws:SourceIp": "192.168.143.0/24"
            "NotIpAddress" : {
                "aws:SourceIp": "192.168.143.188/32"
       }
    }
]
```

Restricting Access to Specific HTTP Referer

The following example policy restricts access based on HTTP Referer.

Example

Granting Permissions to Enable Log Delivery to an S3 Bucket

The following example policy enables log delivery to your Amazon S3 bucket. The account specified in the following policy is the Log Delivery group. You must use the ARN specified in this policy because it identifies the Log Delivery group. For more information, see Setting Up Server Access Logging (p. 320).

Example

```
{
  "Version":"2008-10-17",
  "Id":"LogPolicy",
  "Statement":[{
    "Sid":"Enables the log delivery group to publish logs to your bucket ",
    "Effect":"Allow",
    "Principal":{
        "AWS":"arn:aws:iam::858827067514:root"
        },
        "Action":["s3:GetBucketAcl",
        "s3:GetObjectAcl",
        "s3:PutObject"
        ],
        "Resource":["arn:aws:s3:::example-bucket",
        "arn:aws:s3:::example-bucket/*"
        ]
    }
}
```

Granting Permission, Using Canonical ID, to a CloudFront Origin Identify

The following example bucket policy grants a CloudFront Origin Identity permission to GET all objects in your Amazon S3 bucket. The CloudFront Origin Identity is used to enable CloudFront's private content feature. The policy uses the CanonicalUser prefix, instead of AWS, to specify a Canonical User ID. To learn more about CloudFront's support for serving private content, go to the Serving Private Content topic in the Amazon CloudFront Developer Guide. You must specify the Canonical User ID for your CloudFront distribution's origin access identity.

Example

```
{
  "Version":"2008-10-17",
  "Id":"PolicyForCloudFrontPrivateContent",
  "Statement":[{
    "Sid":" Grant a CloudFront Origin Identity access to support private content",
    "Effect":"Allow",
    "Principal":{
    "CanonicalUser":"79a59df900b949e55d96a1e698fbaced
fd6e09d98eacf8f8d5218e7cd47ef2be"
    },
    "Action":"s3:GetObject",
    "Resource":"arn:aws:s3:::example-bucket/*"
}
]
]
}
```

How to Use Resources, Principals, Operations, and Conditions in Bucket Policies

Topics

- Specifying Amazon S3 Resources in Bucket Policies (p. 222)
- · Specifying Principals in Bucket Policies (p. 223)
- Amazon S3 Actions (p. 223)
- Bucket Keys in Amazon S3 Policies (p. 224)
- Object Keys in Amazon S3 Policies (p. 226)

Specifying Amazon S3 Resources in Bucket Policies

You can refer to buckets and objects in bucket policies. Amazon S3 policies use the Amazon Resource Name (ARN) format for specifying them, as follows:

```
arn:aws:s3:::[resourcename]
```

The resource name is the fully qualified name of a bucket or object that the user is requesting access to. For buckets, the resource name is bucketname, where bucketname is the name of the bucket. For objects, the format for the resource's name is bucketname/keyname, where bucketname is the name of the bucket and keyname is the full name of the object. For example, if you have a bucket called "Ooyala"

Amazon Simple Storage Service Developer Guide How to Use Resources, Principals, Operations, and Conditions in Bucket Policies

and an object with the name shared/developer/settings.conf, the resource name for the bucket would be Ooyala; for the object it would be Ooyala/shared/developer/settings.conf.

Specifying Principals in Bucket Policies

The Principal is one or more people who receive or are denied permission according to the policy. You must specify the principal by using the principal's AWS account ID (e.g., 1234-5678-9012, with or without the hyphens). The AWS account ID can belong to either an AWS Account or an IAM User. You can specify multiple principals, or a wildcard (*) to indicate all possible users. You can view your account ID by logging in to your AWS account at http://aws.amazon.com and clicking **Account Activity** in the **Accounts** tab.

Instead of specifying an AWS account ID you can specify a Canonical User ID when granting permission to an AWS Account. You can view your Canonical User ID by logging in to your AWS account at http://aws.amazon.com and, clicking **Security Credentials** in the **Accounts** tab. You can also grant a CloudFront Origin Access Identify using the Canonical User ID associated with that identify. To learn more about CloudFront's support for serving private content, go to Serving Private Content topic in Amazon CloudFront Developer Guide. You must specify the Canonical User ID for your CloudFront distribution's origin identity, not your AWS Account.

In JSON, you use "AWS": as a prefix for the principal's AWS account ID and the "CanonicalUser": prefix for the principal's AWS Canonical User ID.



Note

When you grant other AWS accounts access to your AWS resources, be aware that the AWS accounts can delegate their permissions to users under their accounts. This is known as cross-account access. For information about using cross-account access, go to Enabling Cross-Account Access in Using Identity and Access Management.

Amazon S3 Actions

The following list shows the format for the Amazon S3 actions that you can reference in a policy.

Actions Related to Objects

- s3:GetObject (covers REST GET Object, REST HEAD Object, REST GET Object torrent, SOAP GetObject, and SOAP GetObjectExtended)
- s3:GetObjectVersion (covers REST GET Object, REST HEAD Object, REST GET Object torrent, SOAP GetObject, and SOAP GetObjectExtended)
- s3:PutObject (covers the REST PUT Object, REST POST Object, REST Initiate Multipart Upload, REST Upload Part, REST Complete Multipart Upload, SOAP PutObject, and SOAP PutObjectInline)
- s3:GetObjectAcl
- s3:GetObjectVersionAcl
- s3:PutObjectAcl
- s3:PutObjectVersionAcl
- s3:DeleteObject
- s3:DeleteObjectVersion
- s3:ListMultipartUploadParts
- s3:AbortMultipartUpload

Actions Related to Buckets

- s3:CreateBucket
- s3:DeleteBucket
- s3:ListBucket
- s3:ListBucketVersions
- s3:ListAllMyBuckets (covers REST GET Service and SOAP ListAllMyBuckets)
- s3:ListBucketMultipartUploads

Actions Related to Bucket Sub-Resources

- s3:GetBucketAcl
- s3:PutBucketAcl
- s3:GetBucketVersioning
- s3:PutBucketVersioning
- s3:GetBucketRequesterPays
- s3:PutBucketRequesterPays
- s3:GetBucketLocation
- s3:PutBucketPolicy
- s3:GetBucketPolicy
- s3:PutBucketNotification
- s3:GetBucketNotification
- s3:GetBucketLogging
- s3:PutBucketLogging

Bucket Keys in Amazon S3 Policies

The following table shows the keys related to buckets that can be in Amazon S3 policies.

Action	Applicable Keys	Description
s3:CreateBucket	s3:x-amz-acl	The Amazon S3 canned ACL that is applied to the bucket. A canned ACL represents a predefined permission that can be applied to the bucket being created. Valid values: private public-read public-read-write authenticated-read bucket-owner-read bucket-owner-full-control log-delivery-write. Example value: public-read
	s3:LocationConstraint	Specifies the Region where the bucket will be created. Valid values are us-west-1 (for Northern California) or EU (for Ireland). Do not specify a value for US Standard. Example value: us-west-1

Amazon Simple Storage Service Developer Guide How to Use Resources, Principals, Operations, and Conditions in Bucket Policies

Action	Applicable Keys	Description
s3:ListBucket	s3:prefix	Limits the response to objects that begin with the specified prefix. Use this to allow or deny access to objects that begin with the prefix. Example value: home
	s3:delimiter	The character you use to group objects. Example value: /
	s3:max-keys	The number of objects to return from the call. The maximum allowed value (and default) is 1000.
		For use with access policy language numeric conditions (for more information, see Numeric Conditions (p. 348)). Example value: 100
s3:ListBucketVersion s	s3:prefix	Header that lets you limit the response to include only keys that begin with the specified prefix. Example value: home
	s3:delimiter	The character you use to group objects. Example value: /
	s3:max-keys	The number of objects to return from the call. The maximum allowed value (and default) is 1000. For use with access policy language numeric conditions (for more information, see Numeric Conditions (p. 348)). Example value: 100
s3:PutBucketAcl	s3:x-amz-acl	The Amazon S3 canned ACL that is applied to the bucket. A canned ACL represents a predefined permission that can be applied to the bucket being created. Valid values: private public-read public-read-write authenticated-read bucket-owner-read bucket-owner-full-control log-delivery-write. Example value: public-read

Object Keys in Amazon S3 Policies

The following list shows the keys related to objects that can be in Amazon S3 policies.

Action	Applicable Keys	Description	
s3:PutObject	s3:x-amz-acl	The Amazon S3 canned ACL that is applied to the object. A canned ACL represents a predefined permission that can be applied to the object being PUT to Amazon S3. Valid values: private public-read public-read-write authenticated-read bucket-owner-read bucket-owner-full-control log-delivery-write. Example value: public-read	
	s3:x-amz-copy-source	The header that specifies the name of the source bucket and key name of the source object, separated by a slash (/). Used when copying an object. Example value: /bucketname/keyname	
	s3:x-amz-metadata-di rective	The header that specifies whether the metadata is copied from the source object or replaced with metadata provided in the request. If copied, the metadata, except for the version ID, remains unchanged. Otherwise, all original metadata is replaced by the metadata you specify. Used when copying an object. Valid values: COPY REPLACE. The default is COPY. Example value: REPLACE	
s3:PutObjectAcl	s3:x-amz-acl	The Amazon S3 canned ACL that is applied to the object. A canned ACL represents a predefined permission that can be applied to the object being PUT to Amazon S3. Valid values: private public-read public-read-write authenticated-read bucket-owner-read bucket-owner-full-control log-delivery-write. Example value: public-read	

Amazon Simple Storage Service Developer Guide How to Use Resources, Principals, Operations, and Conditions in Bucket Policies

Action	Applicable Keys	Description
s3:GetObjectVersion	s3:VersionId	The version ID of the object being retrieved. Example value: Upfdndhfd8438MNFDN93 jdnJFkdmqnh893
s3:GetObjectVersionA cl	s3:VersionId	The version ID of the object ACL being retrieved. Example value: Upfdndhfd8438MNFDN93 jdnJFkdmqnh893
s3:PutObjectVersionA cl	s3:VersionId	The version ID of the object ACL being PUT. Example value: Upfdndhfd8438MNFDN93 jdnJFkdmqnh893
	s3:x-amz-acl	The Amazon S3 canned ACL that is applied to the object. A canned ACL represents a predefined permission that can be applied to the object being PUT to Amazon S3. Valid values: private public-read public-read-write authenticated-read bucket-owner-read bucket-owner-full-control log-delivery-write. Example value: public-read
s3:DeleteObjectVersi on	s3:VersionId	The version ID of the object being deleted. Example value: Upfdndhfd8438MNFDN93 jdnJFkdmqnh893

Using ACLs

Topics

- Access Control List (ACL) Overview (p. 228)
- Managing ACLs (p. 232)
- When to Use ACLs vs Bucket Policies (p. 243)

Access Control List (ACL) Overview

Topics

- Specifying a Grantee (p. 229)
- · Specifying a Permission (p. 230)
- Sample ACL (p. 230)
- Canned ACL (p. 231)

Amazon S3 Access Control Lists (ACL) enable you to manage access to buckets and objects. Each bucket and object has an ACL attached to it as a subresource. It defines which AWS accounts or groups are granted access and the type of access. When a request is received against a resource, Amazon S3 checks the corresponding ACL to verify the requester has the necessary access permissions.

When you create a bucket or an object, Amazon S3 creates a default ACL that grants the resource owner full control over the resource as shown in the following sample bucket ACL (the default object ACL has same structure).

```
<?xml version="1.0" encoding="UTF-8"?>
<AccessControlPolicy xmlns="http://s3.amazonaws.com/doc/2006-03-01/">
  <Owner>
    <ID>*** Owner-Canonical-User-ID ***</ID>
    <DisplayName>owner-display-name/DisplayName>
  </Owner>
  <AccessControlList>
    <Grant>
      <Grantee xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"</pre>
xsi:type="Canonical User">
        <ID>*** Owner-Canonical-User-ID ***</ID>
        <DisplayName>display-name</DisplayName>
      </Grantee>
      <Permission>FULL CONTROL</Permission>
    </Grant>
  </AccessControlList>
</AccessControlPolicy>
```

The sample ACL includes an <code>Owner</code> element identifying the owner via the AWS account's canonical user ID. The <code>Grant</code> element identifies the grantee (either an AWS account or a predefined group), and the permission granted. This default ACL has one <code>Grant</code> element for the owner. You grant permissions by adding <code>Grant</code> elements, identifying the grantee and the permission.



Note

An ACL can have up to 100 grants.

When you send a REST request to create a bucket or add an object, you cannot specify an ACL in the request body. However, Amazon S3 supports adding canned, predefined ACLs. Each canned ACL has predefined set of grantees and permissions. You specify a canned ACL in your request header and Amazon S3 adds the corresponding predefined grants to the resource ACL. For more information, see Canned ACL (p. 231).

Specifying a Grantee

A grantee can be an AWS account or one of the predefined Amazon S3 groups. You grant permission to an AWS account by the email address or the canonical user ID. However, if you provide a email in your grant request, Amazon S3 finds the canonical user ID for that account and adds it to the ACL. The resulting ACLs will always contain the canonical user ID for the AWS account, not the AWS account's email address.

Amazon S3 has a set of predefined groups. When granting account access to a group, you specify one of our URIs instead of a canonical user ID. We provide the following predefined groups:

- Authenticated Users group—Represented by http://acs.amazonaws.com/groups/global/AuthenticatedUsers.
 This group represents all Amazon AWS accounts. Access permission to this group allows any Amazon AWS account to access the resource. However, all requests must be signed (authenticated).
- All Users group—Represented by http://acs.amazonaws.com/groups/global/AllUsers.
 Access permission to this group allows anyone to access the resource. The requests can be signed (authenticated) or unsigned (anonymous). Unsigned requests omit the Authentication header in the request.
- Log Delivery group—Represented by http://acs.amazonaws.com/groups/s3/LogDelivery. WRITE permission on a bucket enables this group to write server access logs (see Server Access Logging (p. 312)) to the bucket.



Note

When using ACLs, a grantee can be an AWS account or one of the predefined Amazon S3 groups. However, the grantee cannot be an IAM User. For more information about AWS users and permissions within IAM, go to Using AWS Identity and Access Management.



Note

When you grant other AWS Accounts access to your resources, be aware that the AWS accounts can delegate their permissions to users under their accounts. This is known as cross-account access. For information about using cross-account access, go to Enabling Cross-Account Access in Using Identity and Access Management.

Finding a Canonical User ID

The canonical user ID is associated with your AWS account. You can find this ID as follows:

To find Canonical User ID

- 1. Go to Security Credentials.
- 2. If you are not already logged in, you are prompted to sign in to Amazon Web Services.
- 3. Go to the **Account Identifier** section for the canonical user ID associated with your AWS account.

Amazon Simple Storage Service Developer Guide Access Control List (ACL) Overview

You can also look up the canonical user ID of AWS accounts by reading the ACL of a bucket or an object to which the AWS account has access permissions. When individual AWS account is granted a permission, there is a grant entry in the ACL with the AWS account's canonical user ID.

Specifying a Permission

The following table lists the set of permissions Amazon S3 supports in an ACL. The table lists the permission and describes what they mean in the context of object and bucket permissions.

Permission	When granted on a bucket	When granted on an object
READ	Allows grantee to list the objects in the bucket	Allows grantee to read the object data and its metadata
WRITE	Allows grantee to create, overwrite, and delete any object in the bucket	Not applicable
READ_ACP	Allows grantee to read the bucket ACL	Allows grantee to read the object ACL
WRITE_ACP	Allows grantee to write the ACL for the applicable bucket	Allows grantee to write the ACL for the applicable object
FULL_CONTROL	Allows grantee the READ, WRITE, READ_ACP, and WRITE_ACP permissions on the bucket	Allows grantee the READ, READ_ACP, and WRITE_ACP permissions on the object

Sample ACL

The following sample ACL on a bucket identifies the resource owner and a set of grants. The format is the XML representation of an ACL in the Amazon S3 REST API. The bucket owner has <code>FULL_CONTROL</code> of the resource. In addition, the ACL shows how permissions are granted on resource to two AWS accounts, identified by canonical user ID, and two of the predefined Amazon S3 groups discussed in the preceding section.

```
<?xml version="1.0" encoding="UTF-8"?>
<AccessControlPolicy xmlns="http://s3.amazonaws.com/doc/2006-03-01/">
  <Owner>
    <ID>Owner-canonical-user-ID</ID>
    <DisplayName>display-name/DisplayName>
  </Owner>
  <AccessControlList>
    <Grant>
      <Grantee xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"</pre>
xsi:type="CanonicalUser">
        <ID>Owner-canonical-user-ID</ID>
        <DisplayName>display-name</DisplayName>
      </Grantee>
      <Permission>FULL_CONTROL</Permission>
    </Grant>
    <Grant>
     <Grantee xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"</pre>
xsi:type="CanonicalUser">
        <ID>user1-canonical-user-ID</ID>
        <DisplayName>display-name</DisplayName>
      </Grantee>
```

Amazon Simple Storage Service Developer Guide Access Control List (ACL) Overview

```
<Permission>WRITE</permission>
    </Grant>
    <Grant>
      <Grantee xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"</pre>
xsi:type="CanonicalUser">
        <ID>user2-canonical-user-ID</ID>
        <DisplayName>display-name</DisplayName>
      </Grantee>
      <Permission>READ</Permission>
    </Grant>
    <Grant>
      <Grantee xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"</pre>
xsi:type="Group">
        <URI>http://acs.amazonaws.com/groups/global/AllUsers</URI>
      </Grantee>
      <Permission>READ</Permission>
    </Grant>
    <Grant>
      <Grantee xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"</pre>
xsi:type="Group">
        <URI>http://acs.amazonaws.com/groups/s3/LogDelivery</URI>
      </Grantee>
      <Permission>WRITE</Permission>
    </Grant>
  </AccessControlList>
</AccessControlPolicy>
```

Canned ACL

Amazon S3 supports a set of predefined ACLs, known as canned ACLs. Each canned ACL has a predefined a set of grantees and permissions. You specify a canned ACL in your request using the x-amz-acl request header. When Amazon S3 receives a request with a canned ACL in the request, it adds the predefined grants to the ACL of the resource. The following table lists the set of canned ACLs and the associated predefined grants.

Canned ACL	Applies to	Permissions added to ACL
private	Bucket and object	Owner gets FULL_CONTROL. No one else has access rights (default).
public-read	Bucket and object	Owner gets FULL_CONTROL. The Allusers group (see Specifying a Grantee (p. 229)) gets the READ access.
public-read-write	Bucket and object	Owner gets FULL_CONTROL. The Allusers group gets READ and WRITE access. Granting this on a bucket is generally not recommended.
authenticated-read	Bucket and object	Owner gets FULL_CONTROL. The AuthenticatedUsers group gets READ access.
bucket-owner-read	Object	Object owner gets FULL_CONTROL. Bucket owner gets READ access. If specified when creating a bucket, Amazon S3 ignores it.

Canned ACL	Applies to	Permissions added to ACL
bucket-owner-full-control	Object	Both the object owner and the bucket owner get FULL_CONTROL over the object. If you specify this canned ACL when creating a bucket, Amazon S3 ignores it.
log-delivery-write	Bucket	The LogDelivery group gets WRITE and the READ_ACP permission on the bucket. For more information on logs, see (Server Access Logging (p. 312)).

The overview section (see Access Control List (ACL) Overview (p. 228)) describes how you can add a grant to an ACL. However, you can also add grant to the ACL of an existing object or a bucket. When creating an object or a bucket, you cannot specify an ACL. instead, you can specify the canned ACL.



Note

You can specify only one of these canned ACLs in your request.

Managing ACLs

Topics

- Managing ACLs in the AWS Management Console (p. 232)
- Managing ACLs Using the AWS SDK for Java (p. 233)
- Managing ACLs Using the AWS SDK for .NET (p. 237)
- Managing ACLs Using the REST API (p. 243)

There are several ways you can add grants to your resource ACL. You can use the AWS Management Console which provides a UI to manage permissions without writing any code. You can use the REST API or use one of the AWS SDKs. These libraries further simplify your programming tasks.

Managing ACLs in the AWS Management Console

AWS Management Console provides a UI for you to grant ACL based access permissions to your buckets and objects. The **Properties** pane includes the following **Permissions** tab.



The tab shows the ACL for your selected resource. that is, it shows the list of grants found in the resource ACL. For each grant, it shows the grantee and a set of check boxes showing the permissions granted. The permission names in the console are different than the ACL permission names (see Specifying a Permission (p. 230)). The preceding illustration shows the mapping between the two.

The preceding illustration shows a grantee with <code>FULL_CONTROL</code> permissions, all the check boxes are selected. All the UI components shown, except the **Add bucket policy** link, relate the ACL based permissions. The UI allows you to add or remove permissions. To add permissions, click **Add more**

permissions, and to delete a permission, highlight the line and click **X** to the right of it. When you are done updating permissions, click Save to update the ACL. The console sends the necessary request to Amazon S3 to update the ACL on the specific resource.

Managing ACLs Using the AWS SDK for Java

The following tasks guide you through using the Java classes to update ACL on an existing bucket.

Updating ACL on Existing Bucket

1	Create an instance of the AmazonS3 class by providing your AWS credentials.
2	Execute the AmazonS3.getBucketAcl or the AmazonS3.getObjectAcl methods. You need to provide the bucket name and object name, if retrieving an object ACL. This returns the existing ACL as an instance of the AccessControlListAccessControlList class.
3	To add a grant, create an instance of the Grant type by providing the grantee and the permission, and add it to your AccessControlList instance. If you are adding several grants, you can first create a Grant collection and then add the collection to the AccessControlList. You can optionally clear all the grants in the AccessControlList you read before adding grants to it.
4	Execute the AmazonS3.setBucketAcl or the AmazonS3.setObjectAcl method. You need to provide the bucket name, key name (if updating object ACL), and the updated AccessControlList instance.

The following Java code sample demonstrates the preceding tasks on a bucket ACL.

```
Collection<Grant> c = new ArrayList<Grant>();
AccessControlList bucketAcl = s3Client.getBucketAcl(bucketName);
// Delete all existing grants from the ACL (optional) and add new grants.
bucketAcl.getGrants().clear();
// Add the bucket owner.
Grant grant0 = new Grant(new Canonic
alGrantee("111b113e7a2f25102679df27bb0ae12b3f85be6f111b936c4393484be31aaaaa"),
                               Permission.FullControl);
c.add(grant0);
// Grant using canonical user id.
Grant grant1 = new Grant(new Canonic
alGrantee("a30716ab7115dcb44a5ef76e9d74b7a20567f63b38c4ba23a47fc05cc442d6aa"),
                          Permission.Write);
c.add(grant1);
// Grant using email.
Grant grant2 = new Grant(new EmailAddressGrantee("user@amazon.com") ,
                              Permission.Read);
c.add(grant2);
// Grant access to a group.
```

```
Grant grant3 = new Grant(GroupGrantee.AllUsers, Permission.Read);
c.add(grant3);

bucketAcl.getGrants().addAll(c);

// Save (i.e. replace) the bucket ACL.
s3Client.setBucketAcl(bucketName, bucketAcl);
```

You cannot specify a canned ACL when creating a bucket or an object. However, you can specify a canned ACL when executing the AmazonS3.setBucketAcl on an existing bucket, as shown in the following Java code sample.

s3Client.setBucketAcl(bucketName, CannedAccessControlList.PublicRead);

Example

The following Java code example first creates a bucket. In the create request, it specifies a public-read canned ACL. It then retrieves the ACL in an AccessControlList instance, clears grants, and adds new grants to the AccessControlList. Finally, it saves the updated AccessControlList, that is, it replaces the bucket ACL subresource.

```
import java.io.IOException;
import java.util.ArrayList;
import java.util.Collection;
import com.amazonaws.AmazonClientException;
import com.amazonaws.AmazonServiceException;
import com.amazonaws.auth.PropertiesCredentials;
import com.amazonaws.services.s3.AmazonS3;
import com.amazonaws.services.s3.AmazonS3Client;
import com.amazonaws.services.s3.model.AccessControlList;
import com.amazonaws.services.s3.model.Bucket;
import com.amazonaws.services.s3.model.CannedAccessControlList;
import com.amazonaws.services.s3.model.CanonicalGrantee;
import com.amazonaws.services.s3.model.CreateBucketRequest;
import com.amazonaws.services.s3.model.EmailAddressGrantee;
import com.amazonaws.services.s3.model.Grant;
import com.amazonaws.services.s3.model.GroupGrantee;
import com.amazonaws.services.s3.model.Permission;
import com.amazonaws.services.s3.model.Region;
public class S3Sample {
private static String bucketName = "*** Provide new bucket name ***";
public static void main(String[] args) throws IOException {
       AmazonS3 s3Client = new AmazonS3Client(new PropertiesCredentials(
                S3Sample.class.getResourceAsStream(
                  "AwsCredentials.properties")));
        Collection<Grant> grantCollection = new ArrayList<Grant>();
        try {
            System.out.println("Downloading an ACL");
            // 1. Create bucket with Canned ACL.
            CreateBucketRequest createBucketRequest =
            new CreateBucketRequest(bucketName, Region.US_Standard);
            Bucket resp = s3Client.createBucket(createBucketRequest);
            // Add public-read using canned ACL.
            s3Client.setBucketAcl(bucketName,
                            CannedAccessControlList.PublicRead);
            // 2. Update ACL on the existing bucket.
            AccessControlList bucketAcl = s3Client.getBucketAcl(bucketName);
            // (Optional) delete all grants.
            bucketAcl.getGrants().clear();
            // Add grant - owner.
            Grant grant0 = new Grant(
```

```
new CanonicalGrantee("*** Provide canonical user ID ***"),
          Permission.FullControl);
        grantCollection.add(grant0);
        // Add grant using canonical user id.
        Grant grant1 = new Grant(
          new CanonicalGrantee("*** Provide canonical user ID ***"),
          Permission.Write);
        grantCollection.add(grant1);
        // Add grant using email.
        Grant grant2 = new Grant(
         new EmailAddressGrantee("*** Provide AWS account email ***"),
          Permission.Read);
        grantCollection.add(grant2);
        // Grant AllUsers group read permission on the bucket.
        Grant grant3 = new Grant(GroupGrantee.AllUsers, Permission.Read);
        grantCollection.add(grant3);
        // Grant LogDelivery group permission to write to the bucket.
        Grant grant4 = new Grant(GroupGrantee.LogDelivery,
                           Permission.Write);
        grantCollection.add(grant4);
        // Grant AuthenticatedUser group permission to update ACL.
        Grant grant5 = new Grant(GroupGrantee.AuthenticatedUsers,
                           Permission.WriteAcp);
        grantCollection.add(grant5);
       bucketAcl.getGrants().addAll(grantCollection);
        // Save (replace) ACL.
        s3Client.setBucketAcl(bucketName, bucketAcl);
    } catch (AmazonServiceException ase) {
        System.out.println("Caught an AmazonServiceException, which" +
          " means your request made it " +
                "to Amazon S3, but was rejected with an error response" +
                " for some reason.");
        System.out.println("Error Message:
                                              " + ase.getMessage());
        System.out.println("HTTP Status Code: " + ase.getStatusCode());
        System.out.println("AWS Error Code: " + ase.getErrorCode());
                                              " + ase.getErrorType());
        System.out.println("Error Type:
        System.out.println("Request ID:
                                              " + ase.getRequestId());
    } catch (AmazonClientException ace) {
        System.out.println("Caught an AmazonClientException, which means"+
          " the client encountered " +
                "a serious internal problem while trying to " +
                "communicate with S3, " +
                "such as not being able to access the network.");
        System.out.println("Error Message: " + ace.getMessage());
    }
}
```

Managing ACLs Using the AWS SDK for .NET

The following tasks guide you through using the C# classes to update ACL on an existing bucket.

Updating ACL on Existing Bucket

1	Create an instance of the AmazonS3 class by providing your AWS credentials.
2	Execute the AmazonS3.GetAcl method to read the existing ACL. You need to provide the resource information, BucketName (if retrieving a bucket ACL) or BucketName and Key name (if retrieving the object ACL). You provide this information using the GetACLRequest object. From the GetACLResponse response, read the S3AccessControlList.
3	To add a grant, execute the S3AccessControlList.AddGrant method by providing the Grantee and the permission values. Before adding new grants, you can optionally clear all the existing grants by calling the S3AccessControlList.Grants.Clear(). Note that this removes all grants including permissions granted to owner. If you clear all the grants, you should regrant the full control grant to the owner.
4	Upload the updated ACL by calling the AmazonS3.SetAcl method. Again, you need to provide the resource information, BucketName (if updating a bucket ACL) or BucketName and Key name (if updating the object ACL using SetACLRequest object).

The following C# code sample demonstrates the preceding tasks. The code sample retrieves an existing bucket ACL, adds new grants to it, and saves the updated ACL.

```
// Get ACL.
GetACLRequest getRequest = new GetACLRequest();
getRequest.BucketName = bucketName;
getRequest.Key = "objectkey";
GetACLResponse getResponse = client.GetACL(getRequest);
S3AccessControlList acl = getResponse.AccessControlList;
getResponse.Dispose();
// Grant permission using email.
S3Grantee grantee1 = new S3Grantee();
granteel.EmailAddress = "*** Email Address ***";
acl.AddGrant(grantee1, S3Permission.WRITE_ACP);
// Grant permission using Canonical ID.
S3Grantee grantee2 = new S3Grantee();
Amazon.S3.Model.Tuple<string, string> t =
         new Amazon.S3.Model.Tuple<string, string>
                ("*** canonical user ID ***", "*** Display Name ***");
grantee2.CanonicalUser = t;
acl.AddGrant(grantee2, S3Permission.WRITE);
// Grant permission to the LogDelivery group.
S3Grantee grantee3 = new S3Grantee();
grantee3.URI = "http://acs.amazonaws.com/groups/s3/LogDelivery";
acl.AddGrant(grantee3, S3Permission.WRITE);
// 1. Now update the ACL.
SetACLRequest request = new SetACLRequest();
request.BucketName = bucketName;
request.ACL = acl;
```

```
SetACLResponse response = client.SetACL(request);
response.Dispose();
```

You can specify a canned ACL (see Canned ACL (p. 231)) when creating a resource. The following C# code sample creates a bucket and specifies a public-read canned ACL in the x-amz-acl request header.

```
PutBucketRequest request = new PutBucketRequest();
request.WithBucketName(bucketName)
    .WithBucketRegion(S3Region.US);
// Add canned acl.
request.AddHeaders(AmazonS3Util.CreateHeaderEntry(
    "x-amz-acl", "public-read"));
client.PutBucket(request).Dispose();
```

Example

The following C# code example first creates a bucket. In the request, it specifies a log-delivery-write canned ACL, granting write permission to the LogDelivery group. It then reads the ACL, cleans existing grants, and adds several grants to AWS accounts—using email, canonical user ID, and existing Amazon S3 groups.

```
using System;
using System.Configuration;
using System.Collections.Specialized;
using Amazon.S3;
using Amazon.S3.Model;
using Amazon.S3.Util;
namespace s3.amazon.com.docsamples.addbucketacl
    class S3Sample
        static string bucketName = "*** Provide Bucket Name ***";
        static AmazonS3 client;
        public static void Main(string[] args)
            if (checkRequiredFields())
                NameValueCollection appConfig =
                    ConfigurationManager.AppSettings;
                string accessKeyID = appConfig["AWSAccessKey"];
                string secretAccessKeyID = appConfig["AWSSecretKey"];
                using (client = Amazon.AWSClientFactory.CreateAmazonS3Client(
                    accessKeyID, secretAccessKeyID))
                {
                    // Add bucket (specify canned ACL).
                    AddBucketWithCannedACL();
                    // Get ACL on a bucket.
                    GetBucketACL(bucketName);
                    // Add (replace) ACL on a bucket.
                    AddACLToExistingBucket();
                }
            }
            Console.WriteLine("Press any key to continue...");
            Console.ReadKey();
        static void GetBucketACL(string bucketName)
            try
                // 1. Get ACL request
                GetACLRequest request = new GetACLRequest();
                request.WithBucketName(bucketName);
                GetACLResponse response = client.GetACL(request);
```

```
S3AccessControlList accessControlList =
                                        response.AccessControlList;
                response.Dispose();
            catch (AmazonS3Exception amazonS3Exception)
                if (amazonS3Exception.ErrorCode != null &&
                    (amazonS3Exception.ErrorCode.Equals("InvalidAccessKeyId")
                    amazonS3Exception.ErrorCode.Equals("InvalidSecurity")))
                {
                    Console.WriteLine("Check the provided AWS Credentials.");
                    Console.WriteLine(
                        "For service sign up go to http://aws.amazon.com/s3");
                else
                    Console.WriteLine(
                        "Error occurred. Message: '{0}' when writing an object"
                        , amazonS3Exception.Message);
                }
            catch (Exception e)
                Console.WriteLine(e.Message);
        }
        static void AddBucketWithCannedACL()
            try
                // 1. Create bucket request
                PutBucketRequest request = new PutBucketRequest();
                request.WithBucketName(bucketName)
                    .WithBucketRegion(S3Region.US);
                // add canned acl
                request.AddHeaders(AmazonS3Util.CreateHeaderEntry(
                                                "x-amz-acl", "log-delivery-
write"));
                client.PutBucket(request).Dispose();
            catch (AmazonS3Exception amazonS3Exception)
                if (amazonS3Exception.ErrorCode != null &&
                    (amazonS3Exception.ErrorCode.Equals("InvalidAccessKeyId")
                    amazonS3Exception.ErrorCode.Equals("InvalidSecurity")))
                {
                    Console.WriteLine("Check the provided AWS Credentials.");
                    Console.WriteLine(
                        "For service sign up go to http://aws.amazon.com/s3");
                }
```

```
else
                   Console.WriteLine(
                       "Error occurred. Message: '{0}' when writing an object"
                       , amazonS3Exception.Message);
           catch (Exception e)
               Console.WriteLine(e.Message);
       }
       static void AddACLToExistingBucket()
           try
           {
               // Get ACL.
               GetACLRequest getRequest = new GetACLRequest();
               getRequest.BucketName = bucketName;
               getRequest.Key = "objectkey";
               GetACLResponse getResponse = client.GetACL(getRequest);
               S3AccessControlList acl = getResponse.AccessControlList;
             // S3AccessControlList acl = client.GetACL(getRequest).AccessCon
trolList;
               getResponse.Dispose();
               // Clear existing grants.
               acl.Grants.Clear();
               // Add grants. First, reset owner's full permission.
               S3Grantee grantee0 = new S3Grantee();
             grantee0.WithCanonicalUser(acl.Owner.Id, acl.Owner.DisplayName);
               acl.AddGrant(grantee0, S3Permission.FULL_CONTROL);
               // Grant permission using email.
               S3Grantee grantee1 = new S3Grantee();
               grantee1.EmailAddress = "user@amazon.com";
               acl.AddGrant(grantee1, S3Permission.WRITE_ACP);
               // Grant permission using Canonical ID.
               S3Grantee grantee2 = new S3Grantee();
               Amazon.S3.Model.Tuple<string, string> t =
                   new Amazon.S3.Model.Tuple<string, string>
name");
               grantee2.CanonicalUser = t;
               acl.AddGrant(grantee2, S3Permission.WRITE);
               // Grant permission to the LogDelivery group.
               S3Grantee grantee3 = new S3Grantee();
             grantee3.URI = "http://acs.amazonaws.com/groups/s3/LogDelivery";
               acl.AddGrant(grantee3, S3Permission.WRITE);
```

```
// Grant permission to the AuthenticatedUser group.
                S3Grantee grantee4 = new S3Grantee();
                grantee4.URI = "http://acs.amazonaws.com/groups/global/Authen
ticatedUsers";
                acl.AddGrant(grantee4, S3Permission.WRITE_ACP);
                // Grant permission to the AuthenticatedUser group.
                S3Grantee grantee5 = new S3Grantee();
              grantee5.URI = "http://acs.amazonaws.com/groups/global/AllUsers";
                acl.AddGrant(grantee5, S3Permission.READ_ACP);
                // 1. Now update the ACL.
                SetACLRequest request = new SetACLRequest();
                request.BucketName = bucketName;
                request.ACL = acl;
                SetACLResponse response = client.SetACL(request);
                response.Dispose();
                // Get and print the updated ACL XML.
                Console.WriteLine(client.GetACL(new GetACLRequest()
                    .WithBucketName(bucketName)).ResponseXml);
            catch (AmazonS3Exception amazonS3Exception)
                if (amazonS3Exception.ErrorCode != null &&
                    (amazonS3Exception.ErrorCode.Equals("InvalidAccessKeyId")
                    amazonS3Exception.ErrorCode.Equals("InvalidSecurity")))
                    Console.WriteLine("Check the provided AWS Credentials.");
                    Console.WriteLine(
                        "For service sign up go to http://aws.amazon.com/s3");
                else
                    Console.WriteLine(
                        "Error occurred. Message: '{0}' when writing an object"
                        , amazonS3Exception.Message);
            catch (Exception e)
                Console.WriteLine(e.Message);
        }
       static bool checkRequiredFields()
            NameValueCollection appConfig = ConfigurationManager.AppSettings;
```

```
if (string.IsNullOrEmpty(appConfig["AWSAccessKey"]))
            Console.WriteLine(
                "AWSAccessKey was not set in the App.config file.");
            return false;
        if (string.IsNullOrEmpty(appConfig["AWSSecretKey"]))
            Console.WriteLine(
                "AWSSecretKey was not set in the App.config file.");
            return false;
        if (string.IsNullOrEmpty(bucketName))
            Console.WriteLine("The variable bucketName is not set.");
            return false;
        }
        if (string.IsNullOrEmpty(keyName))
            Console.WriteLine("The variable keyName is not set.");
            return false;
        return true;
}
```

Managing ACLs Using the REST API

For information on the REST API support for managing ACLs, see the following sections in the *Amazon Simple Storage Service* API Reference:

- GET Bucket acl
- PUT Bucket acl
- GET Object acl
- PUT Object acl

When to Use ACLs vs Bucket Policies

ACLs provide a coarse-grain permission model, where you simply grant access permissions to buckets or objects. Bucket policies, on the other hand, provide fine-grain control over the permissions you are granting. For example, you can write a policy granting users access to a bucket or an object, provided the user sends the request from a specific IP address, or the request arrives after a specific date and time. Depending on your needs, you can use one or both of these permission models. However, there are specific use cases where ACL's may be the most appropriate:

- There is only a Bucket Policy (no Object Policy)—There are times when you will need to grant a wide variety of permissions on each object in your bucket. For example, if you grant write permission on your bucket, others can add objects to your bucket, which you don't have permissions. These new object owners must explicitly grant permissions on these objects before others to access them.
- Bucket Policies are Limited to 20 Kilobytes in Size—If you have a large number of objects and
 users, your bucket policy could reach the 20 K size limit. In this case, you should consider using ACLs
 for additional grants.

Amazon S3 supports both ACLs and bucket policies. If you already use ACLs, there is no need to change. In simpler scenarios, ACLs might provide the appropriate level of permissions for your use case. For example, when granting permissions to a smaller number of grantees, using ACLs might be adequate.

Using ACLs and Bucket Policies Together

When you have ACLs and bucket policies assigned to buckets, Amazon S3 evaluates the existing Amazon S3 ACLs as well as the bucket policy when determining an account's access permissions to an Amazon S3 resource. If an account has access to resources that an ACL or policy specifies, they are able to access the requested resource.

With existing Amazon S3 ACLs, a grant always provides access to a bucket or object. When using policies, a deny always overrides a grant.



Note

Bucket policies have their own set of rules when prioritizing grants and denies. For more information, see Evaluation Logic (p. 338).

You can migrate existing Amazon S3 ACLs to policies.

To migrate ACLs to bucket policies

Associate a policy with a specific user, group, or bucket.

Add a grant to the policy for each Amazon S3 resource that the user or group has been granted access to in the ACL

Once completed, you can begin to manage your account permissions with policies instead of ACLs.

Relationship Between Actions and Permissions

Policies can allow or deny certain actions. ACLs can grant certain permissions. The actions allowed or denied by policies are a superset of the permissions that you can grant by ACLs. The relationship between actions and permissions is summarized in the following sections.

Object ACL Permissions

- **READ**—Granting *READ* permission in an object ACL allows the *s3:GetObject*, *s3:GetObjectVersion*, and *s3:GetObjectTorrent* actions to be performed on that object.
- **READ_ACP**—Granting *READ_ACP* permission in an object ACL allows the *s3:GetObjectAc1* and *s3:GetObjectVersionAc1* actions to be performed on that object.
- WRITE_ACP—Granting WRITE_ACP permission in an object ACL allows the s3:PutObjectAcl and s3:PutObjectVersionAcl actions to be performed on that object.
- FULL_CONTROL—Granting FULL_CONTROL permission in an object ACL is equivalent to granting READ, READ ACP, and WRITE ACP permission.

Bucket ACL Permissions

• **READ**—Granting *READ* permission in a bucket ACL allows the *s3:ListBucket*, *s3:ListBucketVersions*, and *s3:ListBucketMultipartUploads* actions to be performed on that bucket.

Amazon Simple Storage Service Developer Guide Using Query String Authentication

- WRITE—Granting WRITE permission in a bucket ACL allows the s3:PutObject and s3:DeleteObject actions to be performed on any object in that bucket. In addition, when the grantee is the bucket owner, granting WRITE permission in a bucket ACL allows the s3:DeleteObjectVersion action to be performed on any version in that bucket.
- **READ_ACP**—Granting *READ_ACP* permission in a bucket ACL allows the *s3:GetBucketAc1* action to be performed on that bucket.
- WRITE_ACP—Granting WRITE_ACP permission in a bucket ACL allows the s3:PutBucketAcl action to be performed on that bucket.
- FULL_CONTROL—Granting FULL_CONTROL permission in a bucket ACL is equivalent to granting READ, WRITE, READ_ACP, and WRITE_ACP permission.

For more information on the actions that can be allowed or denied by policies, see Writing Bucket Policies (p. 217).

Using Query String Authentication

Query string authentication is useful for giving HTTP or browser access to resources that would normally require authentication. The signature in the query string secures the request. Query string authentication requests require an expiration date. You can specify any future expiration time in epoch or UNIX time (number of seconds since January 1, 1970).

Using Query String Authentication

1	Create a query.
2	Specify an expiration time for the query.
3	Sign it with your signature.
4	Place the data in an HTTP request.
5	Distribute the request to a user or embed the request in a web page

For example, a query URL is similar to the following example.

http://quotes.s3.amazonaws.com/nelson?AWSAccessKeyId=44CF9SAMPLEF252F707&Expires=1177363698&Signature=vjSAMPLENmGa%2ByT272YEAiv4%3D

For information on how to sign requests, see Query String Request Authentication Alternative (p. 57)

Data Protection

Topics

- Using Data Encryption (p. 246)
- Using Reduced Redundancy Storage (p. 260)
- Using Versioning (p. 262)

Amazon S3 provides a highly durable storage infrastructure designed for mission-critical and primary data storage. Objects are redundantly stored on multiple devices across multiple facilities in an Amazon S3 Region. To help ensure data durability, Amazon S3 PUT and PUT Object copy operations synchronously store your data across multiple facilities before returning SUCCESS. Once stored, Amazon S3 maintains the durability of your objects by quickly detecting and repairing any lost redundancy.

Amazon S3 also regularly verifies the integrity of data stored using checksums. If Amazon S3 detects data corruption, it is repaired using redundant data. In addition, Amazon S3 calculates checksums on all network traffic to detect corruption of data packets when storing or retrieving data.

Amazon S3's standard storage is:

- Backed with the Amazon S3 Service Level Agreement
- Designed to provide 99.999999999% durability and 99.99% availability of objects over a given year
- Designed to sustain the concurrent loss of data in two facilities

Amazon S3 further protects your data using versioning. You can use versioning to preserve, retrieve, and restore every version of every object stored in your Amazon S3 bucket. With versioning, you can easily recover from both unintended user actions and application failures. By default, requests retrieve the most recently written version. You can retrieve older versions of an object by specifying a version of the object in a request.

Using Data Encryption

Topics

- Using Server-Side Encryption (p. 247)
- Using Client-Side Encryption (p. 254)

Amazon Simple Storage Service Developer Guide Using Server-Side Encryption

Encryption provides added security for your object data stored in your buckets in Amazon S3. You can encrypt data on your client-side and upload the encrypted data to Amazon S3. In this case, you manage encryption process, the encryption keys, and related tools. Optionally, you might want to use the server-side encryption feature in which Amazon S3 encrypts your object data before saving it on disks in its data centers and decrypts it when you download the objects, freeing you from the tasks of managing encryption, encryption keys, and related tools.

Using Server-Side Encryption

Topics

- API Support for Server-Side Encryption (p. 248)
- Specifying Server-Side Encryption Using the AWS SDK for Java (p. 248)
- Specifying Server-Side Encryption Using the AWS SDK for .NET (p. 249)
- Specifying Server-Side Encryption Using the AWS SDK for PHP (p. 251)
- Specifying Server-Side Encryption Using the AWS SDK for Ruby (p. 253)
- Specifying Server-Side Encryption Using REST API (p. 254)
- Specifying Server-Side Encryption Using the AWS Management Console (p. 254)

Server-side encryption is about data encryption at rest, that is, Amazon S3 encrypts your data as it writes it to disks in its data centers and decrypts it for you when you access it. As long as you authenticate your request and you have access permissions, there is no difference in the way you access encrypted or unencrypted objects. Amazon S3 manages encryption and decryption for you. For example, if you share your objects using a pre-signed URL, the pre-signed URL works the same way for both encrypted and unencrypted objects.

In client-side encryption, you mange encryption/decryption of your data, the encryption keys, and related tools. Server-side encryption is an alternative to client-side encryption in which Amazon S3 manages the encryption of you data freeing you from the tasks of managing encryption and encryption keys.

Amazon S3 uses the 256-bit Advanced Encryption Standard (AES-256) encryption algorithm to encrypt your data on the server-side.

You can specify data encryption at the object level. When you upload an object, you can explicitly specify in your request if you want Amazon S3 to save your object data encrypted. Server-side encryption is optional. Your bucket might contain both encrypted and unencrypted objects. Amazon S3 supports bucket policy that you can use if you require server-side encryption for all objects that are stored in your bucket. For example, the following bucket policy denies upload object (s3:PutObject) permission to everyone if the request does not include the x-amz-server-side-encryption header requesting server-side encryption.

Amazon Simple Storage Service Developer Guide Using Server-Side Encryption

Server-side encryption encrypts only the object data. Any object metadata is not encrypted.

API Support for Server-Side Encryption

The object creation REST APIs (see Specifying Server-Side Encryption Using REST API (p. 254)) provide a request header, x-amz-server-side-encryption that you can use to request server-side encryption. The AWS SDKs also provide wrapper APIs for you to request server-side encryption. You can also use the AWS Management Console to upload objects and request server-side encryption.

Specifying Server-Side Encryption Using the AWS SDK for Java

When using the AWS SDK for Java to upload an object, you can use the <code>ObjectMetadata</code> property of the <code>PutObjectRequest</code> to set the <code>x-amz-server-side-encryption</code> request header (see Specifying Server-Side Encryption Using REST API (p. 254)). When you call the <code>PutObject</code> method of the AmazonS3 client as shown in the following Java code sample Amazon S3 encrypts and saves the data.

In response, Amazon S3 returns the encryption algorithm used for encrypting your object data, which you can check using the <code>getServerSideEncryption</code> method.

For a working sample that shows how to upload an object, see Upload an Object Using the AWS SDK for Java (p. 124). For server-side encryption, add the ObjectMetadata property to your request.

When uploading large objects using multipart upload API, you can request server-side encryption for the object that you are uploading.

- When using the low-level multipart upload API (see Upload a File (p. 140)) to upload a large object, you can specify server-side encryption when you initiate the multipart upload. That is, you add the ObjectMetadata property by calling the InitiateMultipartUploadRequest.setObjectMetadata method.
- When using the high-level multipart upload API (see Using the High-Level Java API for Multipart Upload (p. 135)), the TransferManager class provides methods to upload objects. You can call any of the upload methods that take ObjectMetadata as a parameter.

Determining Encryption Algorithm Used

To determine the encryption state of an existing object you can retrieve the object metadata as shown in the following Java code sample.

If server-side encryption is not used for the object that is stored in Amazon S3, the method returns a null.

Changing Server-Side Encryption of an Existing Object (Copy Operation)

To change the encryption state of an existing object, you make a copy of the object and delete the source object. Note that, by default, the copy API will not encrypt the target, unless you explicitly request server-side encryption. You can request the encryption of the target object by using the <code>ObjectMetadata</code> property to specify server-side encryption in the <code>CopyObjectRequest</code> as shown in the following Java code sample.

For a working sample of how to copy an object, see Copy an Object Using the AWS SDK for Java (p. 175). You can specify server-side encryption in the CopyObjectRequest. object as shown in the preceding code sample.

Specifying Server-Side Encryption Using the AWS SDK for .NET

When using the AWS SDK for .NET to upload an object, you can use the WithServerSideEncryptionMethod property of the PutObjectRequest to set the x-amz-server-side-encryption request header (see Specifying Server-Side Encryption Using REST API (p. 254)). When you call the PutObject method of the AmazonS3 client as shown in the following C# code sample, Amazon S3 encrypts and saves the data.

```
static AmazonS3 client;
client = new AmazonS3Client(accessKeyID, secretAccessKeyID);
PutObjectRequest request = new PutObjectRequest();
```

Amazon Simple Storage Service Developer Guide Using Server-Side Encryption

```
request.WithContentBody("Object data for simple put.")
   .WithBucketName(bucketName)
   .WithKey(keyName)
   .WithServerSideEncryptionMethod(ServerSideEncryptionMethod.AES256);

S3Response response = client.PutObject(request);

// Check the response header to determine if the object is encrypted.
ServerSideEncryptionMethod destinationObjectEncryptionStatus = response.Server
SideEncryptionMethod;
```

In response, Amazon S3 returns the encryption algorithm that is used to encrypt your object data, which you can check using the ServerSideEncryptionMethod property.

For a working sample of how to upload an object, see Upload an Object Using the AWS SDK for .NET (p. 125). For server-side encryption, set the ServerSideEncryptionMethod property by calling the WithServerSideEncryptionMethod method.

To upload large objects using the multipart upload API, you can specify server-side encryption for the objects that you are uploading.

- When using the low-level multipart upload API (see Using the Low-Level .NET API for Multipart Upload (p. 155)) to upload a large object, you can specify server-side encryption in your InitiateMultipartUpload request. That is, you set the ServerSideEncryptionMethod property to your InitiateMultipartUploadRequest by calling the WithServerSideEncryptionMethod method.
- When using the high-level multipart upload API (see Using the High-Level .NET API for Multipart
 Upload (p. 145)), the TransferUtility class provides methods (Upload and UploadDirectory)
 to upload objects. In this case, you can request server-side encryption using the
 TransferUtilityUploadRequest and the TransferUtilityUploadDirectoryRequest objects.

Determining Encryption Algorithm Used

To determine the encryption state of an existing object you can retrieve the object metadata as shown in the following C# code sample.

The encryption algorithm is specified with an enum. If the stored object is not encrypted (default behavior), then the ServerSideEncryptionMethod property of the object will default to None.

Changing Server-Side Encryption of an Existing Object (Copy Operation)

To change the encryption state of an existing object, you can make a copy of the object and delete the source object. Note that by default the copy API will not encrypt the target, unless you explicitly request server-side encryption of the destination object. The following C# code sample makes a copy of an object. The request explicitly specifies server-side encryption for the destination object.

Amazon Simple Storage Service Developer Guide Using Server-Side Encryption

For a working sample of how to copy an object, see Copy an Object Using the AWS SDK for .NET (p. 177). You can specify server-side encryption in the CopyObjectRequest. object as shown in the preceding code sample.

Specifying Server-Side Encryption Using the AWS SDK for PHP

When using the AWS SDK for PHP to upload an object, you can use the $\texttt{AmazonS3::create_object()}$ method to upload an object. To add the x-amz-server-side-encryption request header (see Specifying Server-Side Encryption Using REST API (p. 254)) to your request, specify the array parameter provided by this method. In the array parameter, set the encryption key with value AES256 as shown in the following PHP code sample.

In response, Amazon S3 returns the x-amz-server-side-encryption header with the value of the encryption algorithm used to encrypt your object data.

For a working sample of how to upload an object, see Upload an Object Using the AWS SDK for PHP (p. 129).

To upload large objects using the multipart upload API, you can specify server-side encryption for the objects that you are uploading.

- When using the low-level multipart upload API (see Using the Low-Level PHP API for Multipart Upload (p. 162)), you can specify server-side encryption when you call the AmazonS3::initiate_multipart_upload() method. You add the array parameter and set the encryption key with the value of the encryption algorithm AES256.
- When using the high-level multipart upload API (see Using the High-Level PHP API for Multipart
 Upload (p. 161)), AmazonS3::create_mpu_object(), the API does not support the specification of
 server-side encryption.

Determining Encryption Algorithm Used

To determine the encryption state of an existing object, retrieve the object metadata by calling the <code>get_object_headers</code> method as shown in the following PHP code sample. For the object that is encrypted on the server-side, Amazon S3 returns the <code>x-amz-server-side-encryption</code> header with the value of the encryption algorithm used.

```
$s3 = new AmazonS3();

$response = $s3->get_object_headers($bucket, $keyname);

header('Content-Type: text/plain; charset=utf-8');
print_r($response);

if ($response->isOK())
{
    echo 'Object headers retrieved!';
}
```

Changing Server-Side Encryption of an Existing Object (Copy Operation)

To change the encryption state of an existing object, make a copy of the object and delete the source object. Note that by default the copy API will not encrypt the target, unless you explicitly request server-side encryption of the destination object. You must add the optional array parameter and set the encryption. The following PHP code sample makes a copy of an object. The request explicitly specifies server-side encryption for the destination object.

```
$sourcebucket = '*** Source bucket ***';
$sourcekeyname = '*** Source object key ***';
$targetbucket = '*** Target bucket ***';
$targetkeyname = '*** Target object key ***';
// Instantiate the class.
$s3 = new AmazonS3();
// Copy the object.
$response = $s3->copy_object(
       array( // Source.
           'bucket' => $sourcebucket,
           'filename' => $sourcekeyname
        ),
        array( // Target.
           'bucket' => $targetbucket,
           'filename' => $targetkeyname
           //'encryption' => 'AES256'
        ),
        array( // Optional parameters.
        'encryption' => 'AES256'
);
```

For a working sample of how to copy an object, see Copy an Object Using the AWS SDK for PHP (p. 180).

Specifying Server-Side Encryption Using the AWS SDK for Ruby

When using the AWS SDK for Ruby to upload an object, you can specify that the object be stored at rest encrypted by specifying an options hash server_side_encryption in the #write instance method. When you read the object back, it is automatically decrypted.

The following Ruby script sample demonstrates how to specify that a file uploaded to Amazon S3 be encrypted at rest.

```
# Upload a file and set server-side encryption.
key_name = File.basename(file_name)
s3.buckets[bucket_name].objects[key_name].write(:file => file_name, :serv
er_side_encryption => :aes256)
```

For a working sample that shows how to upload an object, see Upload an Object Using the AWS SDK for Ruby (p. 132).

Determining Encryption Algorithm Used

To check the encryption algorithm that is used for encrypting an object data at rest, use the #server_side_encryption method of the S30bject instance. The following code sample demonstrates how to determine the encryption state of an existing object.

```
# Determine server-side encryption of an object.
enc = s3.buckets[bucket_name].objects[key_name].server_side_encryption
enc_state = (enc != nil) ? enc : "not set"
puts "Encryption of #{key_name} is #{enc_state}."
```

If server-side encryption is not used for the object that is stored in Amazon S3, the method returns a null.

Changing Server-Side Encryption of an Existing Object (Copy Operation)

To change the encryption state of an existing object, make a copy of the object and delete the source object. The Ruby API S30bject class has #copy_from and #copy_to methods that you can use to copy objects. Note that, by default, the copy methods will not encrypt the target, unless you explicitly request server-side encryption. You can request the encryption of the target object by specifying the server_side_encryption value in the options hash argument as shown in the following Ruby code sample. The code sample demonstrates how to use the #copy_to method.

```
# Upload a file and set server-side encryption.
bucket1 = s3.buckets[source_bucket]
bucket2 = s3.buckets[target_bucket]
obj1 = bucket1.objects[source_key]
obj2 = bucket2.objects[target_key]
obj1.copy_to(obj2, :server_side_encryption => :aes256)
```

For a working sample of how to copy an object, see Copy an Object Using the AWS SDK for Ruby (p. 183).

Specifying Server-Side Encryption Using REST API

At the time of object creation, that is, when you are uploading a new object or making a copy of an existing object, you can specify if you want Amazon S3 to encrypt your data by adding the x-amz-server-side-encryption header to the request. Set the value of the header to the encryption algorithm AES256 that Amazon S3 supports. Amazon S3 confirms that your object is stored using server-side encryption by returning the response header x-amz-server-side-encryption.

The following REST upload APIs accept the x-amz-server-side-encryption request header.

- PUT Object
- PUT Object Copy
- POST Object
- · Initiate Multipart Upload

When uploading large objects using the multipart upload API, you can specify server-side encryption by adding the x-amz-server-side-encryption header to the Initiate Multipart Upload request. When copying an existing object, regardless of whether the source object is encrypted or not, the destination object is not encrypted unless you explicitly request server-side encryption.

The response headers of the following REST APIs return the x-amz-server-side-encryption header when an object is stored using server-side encryption.

- PUT Object
- PUT Object Copy
- POST Object
- Initiate Multipart Upload
- Upload Part
- Upload Part Copy
- · Complete Multipart Upload
- · Get Object
- · Head Object

Specifying Server-Side Encryption Using the AWS Management Console

When uploading an object using the AWS Management Console, you can specify server-side encryption. For an example how to upload an object, go to Uploading Objects into Amazon S3.

When you copy an object using the AWS Management Console, the console copies the object as is. That is, if the copy source is encrypted, the target object will be encrypted. For an example of how to copy an object using the console, go to Copying an Object. The console also allows you to update properties of one or more objects. For example, you can select one or more objects and select server-side encryption

Using Client-Side Encryption

Overview

Instead of using Amazon S3's server-side encryption, you also have the option of encrypting your data before sending it to Amazon S3. You can build your own library that encrypts your objects data on the client side before uploading it to Amazon S3. Optionally, you can use the AWS SDK for Java, which you can use to automatically encrypt your data before uploading it to Amazon S3.

Amazon Simple Storage Service Developer Guide Using Client-Side Encryption

Currently, only the AWS SDK for Java supports client-side encryption.



Important

Your private encryption keys and your unencrypted data are never sent to AWS; therefore, it is important that you safely manage your encryption keys. If you lose your encryption keys, you won't be able to unencrypt your data.

The AWS SDK for Java uses a process called *envelope encryption*. In envelope encryption, you provide your encryption key to the Amazon S3 encryption client and the client takes care of the rest of the process. The process works like this:

- 1. The Amazon S3 encryption client generates a one-time-use symmetric key (called the *envelope* symmetric key) that the client uses to encrypt your data.
- 2. The client encrypts the envelope symmetric key using your private encryption key.
- 3. The client then uploads the encrypted envelope key along with your encrypted data to Amazon S3. By default, the encrypted envelope key is stored as object metadata, x-amz-meta-x-amz-key, in Amazon S3.

Retrieving and decrypting the client-side encrypted data from Amazon S3 is the reverse of the encryption flow above:

- 1. The client retrieves your encrypted data from Amazon S3 along with the encrypted envelope key.
- 2. The client then decrypts the encrypted envelope key using your private encryption key.
- 3. The client decrypts your data using the envelope key.

Your private encryption key that the client uses in the envelope encryption process can be an asymmetric key pair (composed of public and private keys) or it can be a symmetric key. We recommend using asymmetric keys for the increased level of security that they provide in the envelope encryption process.

For more information about the envelope encryption process, see the Client-Side Data Encryption with the AWS SDK for Java and Amazon S3 article.

Specifying Client-Side Encryption Using the AWS SDK for Java

To encrypt and decrypt objects client-side for upload to Amazon S3, you can use the AmazonS3EncryptionClient class in the AWS SDK for Java. This class provides similar functionality as the non-encrypted AmazonS3Client class so upgrading existing code to use the encryption client is straightforward.

The AmazonS3EncryptionClient class requires that you initialize it with an EncryptionMaterials instance which describes your encryption keys (either asymmetric or symmetric) to use.



Note

If you get a cipher encryption error message when you use the encryption API for the first time, then your version of the JDK may have a Java Cryptography Extension (JCE) jurisdiction policy file that limits the maximum key length for encryption and decryption transformations to 128 bits. The AWS SDK requires a maximum key length of 256 bits. To check your maximum key length, use the <code>getMaxAllowedKeyLength</code> method of the <code>javax.crypto.Cipher</code> class. To remove the key length restriction, install the Java Cryptography Extension (JCE) Unlimited Strength Jurisdiction Policy Files at the Java SE download page.

Amazon Simple Storage Service Developer Guide Using Client-Side Encryption

Uploading and Retrieving a Client-Side Encrypted Object

1	Construct a new AWSCredentials object by providing your security credentials.
2	Construct a new EncryptionMaterials object by providing asymmetric key pair.
3	Use the AWSCredentials object and the EncryptionMaterials object to create a new AmazonS3EncryptionClient instance.
4	Upload the object using the putObject method and retrieve the object using the getObject method. The client performs the necessary encryption and decryption.

The following Java code sample demonstrates the preceding tasks.

```
// Specify the asymmetric key pair to use.
KeyPairGenerator keyGenerator = KeyPairGenerator.getInstance("RSA");
keyGenerator.initialize(1024, new SecureRandom());
KeyPair myKeyPair = keyGenerator.generateKeyPair();

// Construct an instance of AmazonS3EncryptionClient.
AWSCredentials credentials = new BasicAWSCredentials(myAccessKeyId, mySecretKey);
EncryptionMaterials encryptionMaterials = new EncryptionMaterials(myKeyPair);
AmazonS3EncryptionClient encryptedS3client = new AmazonS3EncryptionClient(credentials, encryptionMaterials);

// Upload the object.
encryptedS3client.putObject(new PutObjectRequest(bucketName, key, createSample File()));

// Retrieve the object.
S3Object downloadedObject = encryptedS3client.getObject(bucketName, key);
```

Example

The following Java code example creates an asymmetric key pair and uses the key pair to upload an encrypted sample file to Amazon S3 and then retrieves the encrypted sample file. You must update the following sample and provide the correct credential information and bucket name.



Note

For demonstration, the following example creates an asymmetric key that is used for the duration the program execution. However, in a real world application, you should already have a key to provide to the client.

```
import java.io.*;
import java.security.*;
import java.security.spec.*;
import com.amazonaws.auth.AWSCredentials;
import com.amazonaws.auth.BasicAWSCredentials;
import com.amazonaws.services.s3.AmazonS3EncryptionClient;
import com.amazonaws.services.s3.model.EncryptionMaterials;
import com.amazonaws.services.s3.model.PutObjectRequest;
import com.amazonaws.services.s3.model.S3Object;
public class S3ClientSideEncryptionTest {
    public static void main(String[] args)
    throws IOException, NoSuchAlgorithmException, InvalidKeySpecException {
        String myAccessKeyId = "***Provide Access Key ID***";
        String mySecretKey = "***Provide Secret Key***";
        String bucketName = "***Provide bucket name***";
        String key = "test.txt";
        String encryptionAlgorithm = "RSA";
       KeyPairGenerator keyGenerator = KeyPairGenerator.getInstance(encryption
Algorithm);
 keyGenerator.initialize(1024, new SecureRandom());
  KeyPair myKeyPair = keyGenerator.generateKeyPair();
        // Construct an instance of AmazonS3EncryptionClient.
        AWSCredentials credentials = new BasicAWSCredentials(myAccessKeyId,
mySecretKey);
        EncryptionMaterials encryptionMaterials = new EncryptionMateri
als(myKeyPair);
        AmazonS3EncryptionClient encryptedS3client =
                            new AmazonS3EncryptionClient(credentials, encryp
tionMaterials);
        // Encrypt and upload a sample file to Amazon S3.
        encryptedS3client.putObject(new PutObjectRequest(bucketName, key, cre
ateSampleFile());
        // Retrieve the file from Amazon S3 and decrypt.
        S30bject downloaded0bject = encryptedS3client.getObject(bucketName,
key);
    private static File createSampleFile() throws IOException {
        File file = File.createTempFile("encryptiontest", ".txt");
```

Amazon Simple Storage Service Developer Guide Using Client-Side Encryption

```
file.deleteOnExit();

Writer writer = new OutputStreamWriter(new FileOutputStream(file));
writer.write(new java.util.Date().toString()+"\n");
writer.write("abcdefghijklmnopqrstuvwxyz\n");
writer.write("01234567890112345678901234\n");
writer.write("!@#$%^&*()-=[]{};':',.<>/?\n");
writer.close();
return file;
}
```

Customizing Your Client-Side Encryption Environment

Client-side encryption using the AWS SDK for Java gives you several options for customizing your encryption/decryption process. This topic discusses how to configure common options and what they mean.

You can configure your client-side encryption environment by choosing the appropriate constructor of the AmazonS3EncryptionClient class. The constructor has several signatures and can take a combination of the following four arguments: AWSCredentials, ClientConfiguration, EncryptionMaterials, and CryptoConfiguration. The AWSCredentials and ClientConfiguration arguments are the same arguments that are used in the non-encrypted Amazon S3 client AmazonS3Client and are not discussed here. The remaining two arguments, EncryptionMaterials and CryptoConfiguration allow you to customize different aspects of your client-side encryption and are discussed below. For more information about the encryption client constructors, see the AWS Java SDK documentation.

Specifying Encryption Materials

To use Amazon S3 client-side encryption, you must specify a key that is used in the encryption process, for both the upload and retrieval of encrypted data. You must keep this key secure.



Important

Your private encryption keys and your unencrypted data are never sent to AWS; therefore, if you lose your encryption keys, you won't be able to unencrypt your data.

You can use the EncryptionMaterials class to indicate to the Amazon S3 encryption client what key you want to use for encryption. You can specify either an asymmetric or symmetric key to use; however, it is recommended that you use an asymmetric key whenever possible. An asymmetric key is a key pair that consists of a public key and a private key.

The following sample code demonstrates how to create a new symmetric key.

```
// Create a new symmetric key.
KeyGenerator symKeyGenerator = KeyGenerator.getInstance("DES");
SecretKey symKey = symKeyGenerator.generateKey();

// Construct an instance of AmazonS3EncryptionClient.
AWSCredentials credentials = new BasicAWSCredentials(myAccessKeyId, mySecretKey);

// Create an EncryptionMaterials object using the symmetric key.
EncryptionMaterials encryptionMaterials = new EncryptionMaterials(symKey);
```

Amazon Simple Storage Service Developer Guide Using Client-Side Encryption

```
// Create a new encryption client.
AmazonS3EncryptionClient encryptedS3 = new AmazonS3EncryptionClient(credentials, encryptionMaterials);
```

Specifying Encryption Metadata Storage Location

When the Amazon S3 client (using the AmazonS3EncryptionClient class) encrypts data and uploads it to Amazon S3, the encrypted envelope symmetric key is also stored in S3. By default, the encrypted key is stored as user-defined object metadata. After you upload an encrypted object, you can view its properties and see the additional metadata name-value pairs related to encryption. For example, the key name **x-amz-meta-x-amz-key** and key value equal to the envelope key are set on an client-side encrypted object uploaded to Amazon S3.

Optionally, you can also choose to store encryption metadata as an *instruction* file stored at the same location as the encrypted file. The instruction file will have the same key name as the encrypted data file but with the extension ".instruction" appended. You should use an instruction file when the strength of your encryption key results in a symmetric key that is too big for the object metadata. Metadata should be less than 2 KB. Encryption metadata is either stored as object metadata or an instruction file, but not both.

The following code sample demonstrates how to store encryption metadata in an instruction file using the CryptoConfiguration class and the appropriate constructor of the AmazonS3EncryptionClient class.

```
// Load the asymmetric key pair.
KeyPair myKeyPair = S3ClientSideEncryptionTest.LoadKeyPair(pathToKey, encrytion
Algorithm);
// Construct an instance of AmazonS3EncryptionClient.
AWSCredentials credentials = new BasicAWSCredentials(myAccessKeyId, mySecretKey);
EncryptionMaterials encryptionMaterials = new EncryptionMaterials(myKeyPair);
// Create an instance of the CryptoConfiguration class to specify using the
instruction file.
CryptoConfiguration cryptoConfig =
   new CryptoConfiguration().withStorageMode(CryptoStorageMode.InstructionFile);
// Use the CryptoConfiguration instance in the encryption client constructor.
AmazonS3EncryptionClient encryptedS3 =
new AmazonS3EncryptionClient(credentials, encryptionMaterials, cryptoConfig);
// Upload the object.
encryptedS3.putObject(new PutObjectRequest(bucketName, key, createSampleFile()));
// Retrieve the object.
S30bject downloaded0bject = encryptedS3.get0bject(bucketName, key);
```

Specifying A Crypto Provider

The default cryptography provider used in Amazon S3 client-side encryption client is the Java Cryptography Extension (JCE). Optionally, you can specify a different cryptography provider implementation to use to encrypt and decrypt data.

The following example sample code demonstrates using the Bouncy Castle provider.

Amazon Simple Storage Service Developer Guide Using Reduced Redundancy Storage

```
// Create a new instance of the provider.
Provider bcProvider = new BouncyCastleProvider();
// Load the asymmetric key pair.
KeyPair myKeyPair = S3ClientSideEncryptionTest.LoadKeyPair(pathToKey, encrytion
Algorithm);
// Construct an instance of AmazonS3EncryptionClient.
AWSCredentials credentials = new BasicAWSCredentials(myAccessKeyId, mySecretKey);
EncryptionMaterials encryptionMaterials = new EncryptionMaterials(myKeyPair);
// Create an instance of the CryptoConfiguration class to specify a crypto
provider.
CryptoConfiguration cryptoConfig =
    new CryptoConfiguration().withCryptoProvider(bcProvider);
// Use the CryptoConfiguration instance in the encryption client constructor.
AmazonS3EncryptionClient encryptedS3 =
new AmazonS3EncryptionClient(credentials, encryptionMaterials, cryptoConfig);
// Upload the object.
encryptedS3.putObject(new PutObjectRequest(bucketName, key, createSampleFile()));
// Retrieve the object.
S30bject downloadedObject = encryptedS3.getObject(bucketName, key);
```

Using Reduced Redundancy Storage

Topics

- Setting the Storage Class of an Object You Upload (p. 260)
- Changing the Storage Class of an Object in Amazon S3 (p. 261)

The Amazon S3 Reduced Redundancy Storage (RRS) option provides a less durable, highly available storage option that is designed to provide 99.99% durability of objects over a given year.

Amazon S3 stores objects according to their storage class, which Amazon S3 assigns to an object when it is written to Amazon S3. The default storage class is STANDARD. You can assign objects a specific storage class (STANDARD or REDUCED_REDUNDANCY) only when writing the objects or when copying objects stored in Amazon S3. RRS is specified per object, at the time the object is written."

For a general overview of this feature, see Reduced Redundancy Storage (p. 6).

Setting the Storage Class of an Object You Upload

To set the storage class of an object you upload to RRS, you set x-amz-storage-class to REDUCED_REDUNDANCY in a PUT request.

How to Set the Storage Class of an Object You're Uploading to RRS

• Create a PUT Object request setting the x-amz-storage-class request header to REDUCED REDUNDANCY.

You must have the correct permissions on the bucket to perform the PUT operation. The default value for the storage class is STANDARD (for regular Amazon S3 storage).

The following example sets the storage class of my-image. jpg to RRS.

```
PUT /my-image.jpg HTTP/1.1
Host: myBucket.s3.amazonaws.com
Date: Wed, 12 Oct 2009 17:50:00 GMT
Authorization: AWS 15B4D3461F177624206A:xQE0diMbLRepdf3YB+FIEXAMPLE=
Content-Type: image/jpeg
Content-Length: 11434
Expect: 100-continue
x-amz-storage-class: REDUCED_REDUNDANCY
```

Changing the Storage Class of an Object in Amazon S3

Topics

Return Code For Lost Data (p. 262)

You can also change the storage class of an object that is already stored in Amazon S3 by copying it to the same key name in the same bucket. To do that, you use the following request headers in a PUT Object copy request:

- x-amz-metadata-directive set to COPY
- x-amz-storage-class set to STANDARD or REDUCED_REDUNDANCY



Important

To optimize the execution of the copy request, do not change any of the other metadata in the PUT Object copy request. If you need to change metadata other than the storage class, set x-amz-metadata-directive to REPLACE for better performance.

How to Rewrite the Storage Class of an Object in Amazon S3

• Create a PUT Object copy request and set the *x-amz-storage-class* request header to REDUCED_REDUNDANCY (for RRS) or STANDARD (for regular Amazon S3 storage), and make the target name the same as the source name.

You must have the correct permissions on the bucket to perform the copy operation.

The following example sets the storage class of my-image.jpg to RRS.

```
PUT /my-image.jpg HTTP/1.1
Host: bucket.s3.amazonaws.com
Date: Wed, 28 Oct 2009 22:32:00 GMT
x-amz-copy-source: /bucket/my-image.jpg
Authorization: AWS 0223123223RW0EXG2:0RQf4/cRonhpaBX5sCYVf1bNRuU=
x-amz-storage-class: REDUCED_REDUNDANCY
x-amz-metadata-directive: COPY
```

The following example sets the storage class of my-image.jpg to standard.

Amazon Simple Storage Service Developer Guide Using Versioning

```
PUT /my-image.jpg HTTP/1.1
Host: bucket.s3.amazonaws.com
Date: Wed, 28 Oct 2009 22:32:00 GMT
x-amz-copy-source: /bucket/my-image.jpg
Authorization: AWS 02236Q123123EXG2:0RQf4/cRonhpaBX5sCYVf1bNRuU=
x-amz-storage-class: STANDARD
x-amz-metadata-directive: COPY
```



Note

If you copy an RSS object and fail to include the x-amz-storage-class request header, the storage class of the target object defaults to STANDARD.

It is not possible to change the storage class of a specific version of an object. When you copy it, Amazon S3 gives it a new version ID.



Note

When an object is written in a copy request, the entire object is rewritten in order to apply the new storage class.

For more information about versioning, see Using Versioning (p. 262).

Return Code For Lost Data


If Amazon S3 detects that an object has been lost, any subsequent GET, or HEAD operations, or PUT Object copy operation that uses the lost object as the source object, will result in a 405 Method Not Allowed error. Once an object is marked lost, Amazon S3 will never be able to recover the object. In this situation, you can either delete the key, or upload a copy of the object."

Using Versioning

Topics

- Enabling a Bucket's Versioning State (p. 263)
- Adding Objects to Versioning-Enabled Buckets (p. 267)
- Listing the Objects in a Versioning-Enabled Bucket (p. 268)
- Retrieving Object Versions (p. 269)
- Deleting Object Versions (p. 271)
- Restoring Previous Versions (p. 276)
- Versioned Object Permissions and ACLs (p. 277)
- Working with Versioning-Suspended Buckets (p. 278)

Versioning is a means of keeping multiple variants of an object in the same bucket. In one bucket, for example, you can have two objects with the same key, but different version IDs, such as photo.gif (version 111111) and photo.gif (version 121212).



You might enable versioning to prevent objects from being deleted or overwritten by mistake, or to archive objects so that you can retrieve previous versions of them.



Note

The SOAP API does not support versioning.

Enabling a Bucket's Versioning State

Topics

- MFA Delete (p. 263)
- Enabling Versioning (p. 264)
- Suspending Versioning (p. 265)
- Determining the Versioning State (p. 266)

Buckets can be in one of three states: unversioned (the default), versioning-enabled, or versioning-suspended. Once you version enable a bucket, it can never return to an unversioned state. You can, however, suspend versioning on that bucket.

Only the bucket owner can configure the versioning state of a bucket. The versioning state applies to all (never some) of the objects in that bucket. The first time you enable a bucket for versioning, objects in it are thereafter always versioned and given a unique version ID.

MFA Delete

You can add another layer of security by configuring a bucket to enable MFA (Multi-Factor Authentication) Delete. By enabling MFA Delete on your Amazon S3 bucket, you can only change the versioning state of your bucket or permanently delete an object version when you provide two forms of authentication together:

- · Your AWS account credentials
- The concatenation of a valid serial number, a space, and the six-digit code displayed on an approved authentication device

To use MFA Delete, you must purchase a third-party device that automatically updates the authentication code displayed on it, as shown.




For more information on how to purchase and activate an authentication device, go to http://aws.amazon.com/mfa/.

Enabling Versioning

Topics

Configuring a Bucket with MFA Delete (p. 264)

Objects stored in your bucket before you set the versioning state have a version ID of null. When you enable versioning the objects in your bucket do not change, as shown in the following figure.



What changes is how Amazon S3 handles the objects in future requests in that bucket.

To enable object versioning

- 1. In a PUT Bucket request, include the versioning sub-resource.
- 2. In the body of the request, use Enabled for the value of the Status request element.

Example Enabling Versioning

The following request enables versioning on the bucket, bucketName.

Configuring a Bucket with MFA Delete


You have the option of enabling MFA Delete at the same time you specify the versioning state of the bucket. Once you configure a bucket so that it is MFA Delete enabled, all future requests to change the versioning state or delete a version require the request header x-amz-mfa: [SerialNumber] [AuthenticationCode]. Note the space between [SerialNumber] and [AuthenticationCode]. Requests that include x-amz-mfa must use HTTPS.

Example Enabling Versioning and MFA Delete

The following request enables versioning and MFA Delete on bucketName.

Suspending Versioning

The bucket owner can suspend versioning to stop accruing object versions. When you suspend versioning, the objects in your bucket do not change, as shown in the following figure.



What changes is how Amazon S3 handles objects in future requests. For a more detailed explanation of the effects of suspending versioning, see Working with Versioning-Suspended Buckets (p. 278).

To suspend object versioning

- 1. In the header of a PUT Bucket request, include the versioning sub-resource.
- 2. In the body of the request, use Suspended for the value of the Status request element.

Example Suspending Versioning

The following request suspends versioning on bucketName.

If you configured a bucket to be MFA Delete enabled, you must include the x-amz-mfa request header and the MfaDelete request element in the request to change the bucket's versioning state.

Example Suspending Versioning Using MFA Delete

The following request suspends versioning on bucketName that is configured with MFA Delete.

Note that requests that include x-amz-mfa must use HTTPS.

Determining the Versioning State

You can use the versioning sub-resource to retrieve the versioning state of a bucket.

To retrieve the versioning state of a bucket

1. In the header of a GET Bucket request, include the *versioning* sub-resource.

```
GET /?versioning HTTP/1.1

Host: bucketName.s3.amazonaws.com

Date: Wed, 12 Oct 2009 17:50:00 GMT

Authorization: AWS 15B4D3461F177624206A:xQE0diMbLRepdf3YB+FIEXAMPLE=

Content-Type: text/plain
```

- 2. In the response, check the value of the response element <code>Status</code>. There are three possible results:
 - If Versioning on a bucket is enabled, the response is:

<VersioningConfiguration xmlns="http://s3.amazonaws.com/doc/2006-03-01/">
 <Status>Enabled</Status>
</VersioningConfiguration>

If Versioning on a bucket is suspended, the response is:

```
<VersioningConfiguration xmlns="http://s3.amazonaws.com/doc/2006-03-01/">
    <Status>Suspended</Status>
</VersioningConfiguration>
```


If Versioning on a bucket has never been enabled, the response doesn't retrieve a status element:

<VersioningConfiguration xmlns="http://s3.amazonaws.com/doc/2006-03-01/"/>

Adding Objects to Versioning-Enabled Buckets

Once you enable versioning on a bucket, Amazon S3 automatically adds a unique version ID to every object stored (using PUT, POST, or COPY) in the bucket.

The following figure shows that Amazon S3 adds a unique version ID to an object when it is added to a versioning-enabled bucket.



Adding Objects to Versioning-Enabled Buckets

- 1 Enable versioning on a bucket using a PUT Bucket versioning request. For more information, go to PUT Bucket versioning.
- 2 Send a PUT, POST, or COPY request to store an object in the bucket.

When you add an object to a versioning-enabled bucket, Amazon S3 returns the version ID of the object in the x-amz-versionid response header, for example:

x-amz-version-id: 3/L4kqtJlcpXroDTDmJ+rmSpXd3dIbrHY



Note

Normal Amazon S3 rates apply for every version of an object stored and transferred. Each version of an object is the entire object; it is not just a diff from the previous version. Thus, if you have three versions of an object stored, you are charged for three objects.

Listing the Objects in a Versioning-Enabled Bucket

Topics

• Retrieving a Subset of Objects in Buckets (p. 268)

To list all of the versions of all of the objects in a bucket, you use the *versions* sub-resource in a GET Bucket request. Amazon S3 can only retrieve a maximum of 1000 objects, and each object version counts fully as an object. Therefore, if a bucket contains two keys (e.g. photo.gif and picture.jpg), and the first key has 990 versions and the second key has 400 versions; a single request would retrieve all 990 versions of photo.gif and only the most recent 10 versions of picture.jpg.

Amazon S3 returns object versions in the order in which they were stored, with the most recently stored returned first.

To list all object versions in a bucket

• In a GET Bucket request, include the versions sub-resource.

```
GET /?versions HTTP/1.1
Host: bucketName.s3.amazonaws.com
Date: Wed, 28 Oct 2009 22:32:00 +0000
Authorization: AWS 02236Q3V0WHVSRW0EXG2:0RQf4/cRonhpaBX5sCYVf1bNRuU=
```

Retrieving a Subset of Objects in Buckets

Topics

- Retrieving All Versions of a Key (p. 268)
- Retrieving Additional Object Versions after Exceeding Max-Keys (p. 269)

There might be times when you either want to retrieve a subset of all object versions in a bucket, or the number of object versions exceeds the value for max-key (1000 by default), so that you have to submit a second request to retrieve the remaining object versions. To retrieve a subset of object versions, you must use the request parameters for GET Bucket. For more information, go to GET Bucket.

Retrieving All Versions of a Key

You can retrieve all versions of an object using the *versions* sub-resource and the *prefix* request parameter using the following process. For more information about *prefix*, go to GET Bucket.

Retrieving All Versions of a Key

- 1 Set the *prefix* parameter to the key of the object you want to retrieve.
- 2 Send a GET Bucket request using the versions sub-resource and prefix.

 GET /?versions&prefix=objectName HTTP/1.1

Amazon Simple Storage Service Developer Guide Retrieving Object Versions

Example Retrieving Objects Using Prefix

The following example retrieves objects whose key is or begins with myObject.

```
GET /?versions&prefix=myObject HTTP/1.1

Host: bucket.s3.amazonaws.com

Date: Wed, 28 Oct 2009 22:32:00 GMT

Authorization: AWS 02236Q3V0WHVSRW0EXG2:0RQf4/cRonhpaBX5sCYVf1bNRuU=
```

You can use the other request parameters to retrieve a subset of all versions of the object. For more information, go to GET Bucket.

Retrieving Additional Object Versions after Exceeding Max-Keys

If the number of objects that could be returned in a GET request exceeds the value of max-keys, the response contains <isTruncated>true</isTruncated>, and includes the first key (in NextKeyMarker) and the first version ID (in NextVersionIdMarker) that satisfy the request, but were not returned. You use those returned values as the starting position in a subsequent request to retrieve the additional objects that satisfy the GET request.

Use the following process to retrieve additional objects that satisfy the original GET Bucket versions request from a bucket. For more information about key-marker, version-id-marker, NextKeyMarker, and NextVersionIdMarker, go to GET Bucket.

Retrieving Additional Responses that Satisfy the Original GET Request

Set the value of key-marker to the key returned in NextKeyMarker in the previous response.
 Set the value of version-id-marker to the version ID returned in NextVersionIdMarker in the previous response.
 Send a GET Bucket versions request using key-marker and version-id-marker.

Example Retrieving Objects Starting with a Specified Key and Version ID


```
GET /?versions&key-marker=myObject&version-id-marker=298459348571 HTTP/1.1 Host: bucket.s3.amazonaws.com
Date: Wed, 28 Oct 2009 22:32:00 GMT
Authorization: AWS 02236Q3V0WHVSRW0EXG2:0RQf4/cRonhpaBX5sCYVf1bNRuU=
```

Retrieving Object Versions


Topics

Retrieving the Metadata of an Object Version (p. 271)

A simple GET request retrieves the latest version of an object. The following figure shows how GET returns the latest version of the object, photo.gif.



To retrieve a specific version, you have to specify its version ID. The following figure shows that a GET versionId request retrieves the specified version of the object (not necessarily the latest).



To retrieve a specific object version

- 1. Set *versionId* to the ID of the version of the object you want to retrieve.
- 2. Send a GET Object versionId request.

Example Retrieving a Versioned Object

The following request retrieves version L4kqtJlcpXroDTDmpUMLUo of my-image.jpg.

GET /my-image.jpg?versionId=L4kqtJlcpXroDTDmpUMLUo HTTP/1.1 Host: bucket.s3.amazonaws.com

Date: Wed, 28 Oct 2009 22:32:00 GMT

Authorization: AWS 02236Q3V0WHVSRW0EXG2:0RQf4/cRonhpaBX5sCYVf1bNRuU=

Retrieving the Metadata of an Object Version

If you only want to retrieve the metadata of an object (and not its content), you use the HEAD operation. By default, you get the metadata of the most recent version. To retrieve the metadata of a specific object version, you specify its version ID.

To retrieve the metadata of an object version

- 1. Set versionId to the ID of the version of the object whose metadata you want to retrieve.
- 2. Send a HEAD Object versionId request.

Example Retrieving the Metadata of a Versioned Object

The following request retrieves the metadata of version 3HL4kqCxf3vjVBH40Nrjfkd of my-image.jpg.

```
HEAD /my-image.jpg?versionId=3HL4kqCxf3vjVBH40Nrjfkd HTTP/1.1
Host: bucket.s3.amazonaws.com
Date: Wed, 28 Oct 2009 22:32:00 GMT
Authorization: AWS 02236Q3V0WpaBX5sCYVf1bNRuU=
```

The following shows a sample response.

```
HTTP/1.1 200 OK
x-amz-id-2: ef8yU9AS1ed4OpIszj7UDNEHGran
x-amz-request-id: 318BC8BC143432E5
x-amz-version-id: 3HL4kqtJlcpXroDTDmjVBH40Nrjfkd
Date: Wed, 28 Oct 2009 22:32:00 GMT
Last-Modified: Sun, 1 Jan 2006 12:00:00 GMT
ETag: "fba9dede5f27731c9771645a39863328"
Content-Length: 434234
Content-Type: text/plain
Connection: close
Server: AmazonS3
```

Deleting Object Versions


Topics

- Using MFA Delete (p. 273)
- Working With Delete Markers (p. 273)
- Removing Delete Markers (p. 274)


A DELETE request has the following use cases:

- When versioning is enabled, a simple DELETE cannot permanently delete an object.
 Instead, Amazon S3 inserts a delete marker in the bucket and that becomes the latest version of the object with a new ID. When you try to GET an object whose latest version is a delete marker, Amazon S3 behaves as though the object has been deleted (even though it has not been erased) and returns a 404 error.
- To permanently delete versioned objects, you must use <code>DELETE Object versionId</code>.

The following figure shows that a simple DELETE does not actually remove the specified object. Instead, Amazon S3 inserts a delete marker.



The following figure shows that deleting a specified object version permanently removes that object.



To a delete a specific version of an object

• In a DELETE request specify a version ID.

Example Deleting a Specific Version

The following example shows how to delete version UIORUnfnd89493jJFJ of photo.gif.

DELETE /photo.gif?versionId=UIORUnfnd89493jJFJ HTTP/1.1

Host: bucket.s3.amazonaws.com

Date: Wed, 12 Oct 2009 17:50:00 GMT

Authorization: AWS 15B4D3461F177624206A:xQE0diMbLRepdf3YB+FIEXAMPLE=

Content-Type: text/plain

Content-Length: 0

Using MFA Delete

If a bucket's versioning configuration is MFA Delete enabled, the bucket owner must include the x-amz-mfa request header in requests to permanently delete an object version or change the versioning state of the bucket. The header's value is the concatenation of your authentication device's serial number, a space, and the authentication code displayed on it. If you do not include this request header, the request fails.

Requests that include x-amz-mfa must use HTTPS.

For more information about authentication devices, go to http://aws.amazon.com/mfa/.

Example Deleting an Object from an MFA Delete Enabled Bucket

The following example shows how to delete my-image.jpg (with the specified version), which is in a bucket configured with MFA Delete enabled.

```
DELETE /my-image.jpg?versionId=3HL4kqCxf3vjVBH40Nrjfkd HTTPS/1.1
Host: bucketName.s3.amazonaws.com
x-amz-mfa: 20899872 301749
Date: Wed, 28 Oct 2009 22:32:00 GMT
Authorization: AWS 02236Q3V0WpaBX5sCYVf1bNRuU=
```

Note the space between [SerialNumber] and [AuthenticationCode]. For more information, go to DELETE Object.

Working With Delete Markers

A delete marker is a placeholder (marker) for a versioned object that was named in a simple DELETE request. Because the object was in a versioning-enabled bucket, the object was not deleted. The delete marker, however, makes Amazon S3 behave as if it had been deleted.

A delete marker is like any other object (it has a key and version ID) except that it:


- · Does not have data associated with it
- · Is not associated with an access control list (ACL) value
- Does not retrieve anything from a GET request because it has no data; you get a 404 error
- The only operation you can use on a delete marker is DELETE and only the bucket owner can issue such a request

Only Amazon S3 can create a delete marker, and it does so whenever you send a <code>DELETE</code> <code>Object</code> request on an object in a versioning-enabled or suspended bucket. The object named in the <code>DELETE</code> request is not actually deleted, instead the delete marker becomes the latest version of the object. (The object's key becomes the key of the Delete Marker.) If you try to get an object and its latest version is a delete marker, Amazon S3 responds with:


- A 404 (Object not found) error
- A response header, x-amz-delete-marker: true

The response header tells you that the object accessed was a delete marker. This response header never returns false; if the value is false, Amazon S3 does not include this response header in the response.

The following figure shows how a simple GET on an object, whose latest version is a delete marker, returns a 404 No Object Found error.




The only way to list delete markers (and other versions of an object) is by using the versions sub-resource in a GET Bucket versions request. A simple GET does not retrieve delete marker objects. The following figure shows that a GET Bucket request does not return objects whose latest version is a delete marker.



Removing Delete Markers


To delete a delete marker, you must specify its version ID in a DELETE Object versionId request. If you use DELETE to delete a delete marker (without specifying the version ID of the delete marker), Amazon S3 does not delete the delete marker, but instead, inserts another delete marker.

The following figure shows how a simple DELETE on a delete marker removes nothing, but adds a new delete marker to a bucket.



In a versioning-enabled bucket, this new delete marker would have a unique version ID. So, it's possible to have multiple delete markers of the same object in one bucket.

To permanently delete a delete marker, you must include its version ID in a DELETE Object versionId request. The following figure shows how a DELETE Object versionId request permanently removes a delete marker. Only the owner of a bucket can permanently remove a delete marker.



The effect of removing the delete marker is that a simple GET request will now retrieve the latest version (121212) of the object.

To permanently remove a delete marker

- 1. Set <code>versionId</code> to the ID of the version to the delete marker you want to remove.
- 2. Send a DELETE Object versionId request.

Amazon Simple Storage Service Developer Guide Restoring Previous Versions

Example Removing a Delete Marker

The following example removes the delete marker for photo.gif version 4857693.

DELETE /photo.gif?versionId=4857693 HTTP/1.1
Host: bucket.s3.amazonaws.com
Date: Wed, 28 Oct 2009 22:32:00 GMT
Authorization: AWS 02236Q3V0WHVSRW0EXG2:0RQf4/cRonhpaBX5sCYVf1bNRuU=

When you delete a delete marker, Amazon S3 includes in the response:

```
204 NoContent
x-amz-version-id: versionID
x-amz-delete-marker: true
```



Note

Delete markers accrue a nominal charge for storage in Amazon S3. Delete markers are equal to the size of your key name, e.g., a Delete Marker for the key "photo.gif" adds 9 bytes of storage to your bucket.


Restoring Previous Versions

One of the value propositions of versioning is the ability to retrieve previous versions of an object. There are two approaches to doing so:

- Copy a previous version of the object into the same bucket


 The copied object becomes the latest version of that object and all object versions are preserved.
- Permanently delete the latest version of the object
 When you delete the latest object version you, in effect, turn the previous version into the latest version of that object.

Because all object versions are preserved, you can make any earlier version the latest version by copying a specific version of the object into the same bucket. In the following figure, the source object (ID = 111111) is copied into the same bucket. Amazon S3 supplies a new ID (88778877) and it becomes the latest version of the object. So, the bucket has both the original object version (111111) and its copy (88778877).



A subsequent GET will retrieve version 88778877.

The following figure shows how deleting the latest version (121212) of an object, which leaves the previous version (111111) as the latest object.



A subsequent \mathtt{GET} will retrieve version 111111.

Versioned Object Permissions and ACLs

Permissions are set at the version level. Each version has its own object owner—whoever PUT the version. So, you can set different permissions for different versions of the same object. To do so, you must specify the version ID of the object whose permissions you want to set in a PUT Object versionId acl request. For a detailed description and instructions on using ACLs, see Authentication and Access Control (p. 204).

Example Setting Permissions for an Object Version

The following request sets the permission of the grantee, BucketOwner@amazon.com, to FULL_CONTROL on the key, my-image.jpg, version ID, 3HL4kqtJvjVBH40Nrjfkd.

```
PUT /my-image.jpg?acl&versionId=3HL4kqtJvjVBH40Nrjfkd HTTP/1.1
Host: bucket.s3.amazonaws.com
Date: Wed, 28 Oct 2009 22:32:00 GMT
Authorization: AWS 02236Q3V0WHVSRW0EXG2:0RQf4/cRonhpaBX5sCYVf1bNRuU=
Content-Length: 124
<AccessControlPolicy>
  <Owner>
    <ID>8a6925ce4adf5f21c32aa379004fef</ID>
    <DisplayName>mtd@amazon.com</DisplayName>
  </Owner>
  <AccessControlList>
    <Grant>
      <Grantee xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"</pre>
xsi:type="CanonicalUser">
       <ID>8a6925ce4adf588a4532142d3f74dd8c71fa124b1ddee97f21c32aa379004fef</ID>
        <DisplayName>BucketOwner@amazon.com</DisplayName>
      </Grantee>
      <Permission>FULL_CONTROL</permission>
    </Grant>
  </AccessControlList>
  </AccessControlPolicy>
```

Likewise, to get the permissions of a specific object version, you must specify its version ID in a GET Object versionId acl request. You need to include the version ID because, by default, GET Object acl returns the permissions of the latest version of the object.

Example Retrieving the Permissions for a Specified Object Version

In the following example, Amazon S3 returns the permissions for the key, my-image.jpg, version ID, DVBH40Nr8X8gUMLUo.

```
GET /my-image.jpg?versionId=DVBH40Nr8X8gUMLUo&acl HTTP/1.1
Host: bucket.s3.amazonaws.com
Date: Wed, 28 Oct 2009 22:32:00 GMT
Authorization: AWS 02236Q3V0WHVSRW0EXG2:0RQf4/cRonhpaBX5sCYVf1bNRuU
```

For more information, go to GET Object acl.

Working with Versioning-Suspended Buckets

Topics

- Adding Objects to Versioning-Suspended Buckets (p. 279)
- Retrieving Objects from Versioning-Suspended Buckets (p. 280)
- Deleting Objects from Versioning-Suspended Buckets (p. 281)

You suspend versioning to stop accruing new versions of the same object in a bucket. You might do this because you only want a single version of an object in a bucket, or you might not want to accrue charges for multiple versions.



Note


It is possible to have versioned objects in a versioning-suspended bucket if the objects were added when the bucket was versioning-enabled.

The following sections describe the behavior of buckets and objects when versioning is suspended.

Adding Objects to Versioning-Suspended Buckets

Once you suspend versioning on a bucket, Amazon S3 automatically adds a null version ID to every subsequent object stored thereafter (using PUT, POST, or COPY) in that bucket.


The following figure shows how Amazon S3 adds the version ID of null to an object when it is added to a version-suspended bucket.




Versioning Suspended

If a null version is already in the bucket and you add another object with the same key, the added object overwrites the original null version.

If there are versioned objects in the bucket, the version you PUT becomes the latest version of the object. The following figure shows how adding an object to a bucket that contains versioned objects does not overwrite the object already in the bucket. In this case, version 111111 was already in the bucket. Amazon S3 attaches a version ID of null to the object being added and stores it in the bucket. Version 111111 is not overwritten.



If a null version already exists in a bucket, the null version is overwritten, as shown in the following figure.




Note that although the key and version ID (null) of null version are the same before and after the PUT, the contents of the null version originally stored in the bucket is replaced by the contents of the object PUT into the bucket.

Adding Objects to Version-Suspended Buckets

- Suspend versioning on a bucket using a PUT Bucket versioning request. For more information, go to PUT Bucket versioning.
- 2 Send a PUT, POST, or COPY request to store an object in the bucket.

Retrieving Objects from Versioning-Suspended Buckets

A GET Object request returns the latest version of an object whether you've enabled versioning on a bucket or not. The following figure shows how a simple GET returns the latest version of an object.



Example Retrieving the Latest Version

The following request retrieves the latest version of photo.gif.


GET /photo.gif HTTP/1.1
Host: bucket.s3.amazonaws.com
Date: Wed, 28 Oct 2009 22:32:00 GMT
Authorization: AWS 02236Q3V0WHVSRW0EXG2:0RQf4/cRonhpaBX5sCYVf1bNRuU=

Deleting Objects from Versioning-Suspended Buckets

If versioning is suspended, a DELETE request:


- Can only remove an object whose version ID is null
 Doesn't remove anything if there isn't a null version of the object in the bucket.
- · Inserts a delete marker into the bucket

The following figure shows how a simple DELETE removes a null version and Amazon S3 inserts a delete marker in its place with a version ID of null.




Remember that a delete marker doesn't have content so you lose the content of the null version when a delete marker replaces it.

The following figure shows a bucket that doesn't have a null version. In this case, the DELETE removes nothing; Amazon S3 just inserts a delete marker.



Even in a versioning-suspended bucket the bucket owner can permanently delete a specified version. The following figure shows that deleting a specified object version permanently removes that object. Only the bucket owner can delete a specified object version.



Hosting Websites on Amazon S3

Topics

- Setting Up a Website (p. 284)
- Website Endpoints (p. 285)
- Index Document Support (p. 287)
- Custom Error Document Support (p. 288)
- How Do I Configure My Bucket As a Website? (p. 290)
- Permissions Required for Website Access (p. 290)

Video available <a>I

AWS provides several features that make it easier to host static websites on Amazon S3. Hosting both the website and data in Amazon S3 helps simplify your management of your website. This support includes the following features:

- **Index document support**—An index document is the document Amazon S3 returns when requests are made to the root or the subfolder of your website. When configuring a bucket as a website, you must provide an index document name.
- Error document support—Should an error occur, Amazon S3 returns an HTML error document. For 4XX class errors, you can optionally configure your own custom error document, enabling you to provide additional guidance to your users.

To use these features, you must configure your Amazon S3 bucket as a website and reference your content using the appropriate website endpoint. When you configure a bucket as a website, it is available only via the region-specific website endpoint where the bucket resides. Amazon S3 provides a set of HTTP endpoints for customers who want to take advantage of the new website hosting capabilities without impacting requests to the existing Amazon S3 REST endpoints. The Amazon S3 REST API continues to behave as before, regardless of whether your bucket is configured to host a website.

The topics in this section provide step-by-step instructions to configure your bucket as a website, describe the endpoints to access the website, and configure permissions required for website access.

Setting Up a Website

This section walks you through the steps of hosting a website on Amazon S3. In the following procedure you use the AWS Management Console to perform the necessary tasks.



Important

In this section, we assume you are already familiar with creating and manipulating Amazon S3 buckets with the console. For more information about creating buckets, see Creating a Bucket.

To host a simple, new website

- 1. Create a bucket and configure it as a website:
 - a. Go to the Amazon S3 tab on the AWS Management Console.
 - b. Create a bucket. Note the region where you created the bucket. In this procedure you create a bucket in the US Standard region.
 - c. In the bucket Properties pane, click the Website configuration tab.
 - d. Select the Enabled check box.
 - e. In the **Index Document Suffix** text box, add the required index document name (index.html). Instructions to upload your index document are provided in the following steps.
 - f. Click Save to save the website configuration.
- 2. Add a bucket policy to make your bucket content publicly available.

The content you want to served via the website endpoint must be publicly readable. You can grant the necessary permissions by adding a bucket policy or by changing each object's ACL. Here we describe adding a bucket policy.

- a. In bucket **Properties** pane, click the **Permissions** tab.
- b. Click Add Bucket Policy.
- c. Copy the following bucket policy and paste it in the **Bucket Policy Editor**.

- d. Update the policy by providing your bucket name, instead of the example-bucket.
- e. Click Save.
- 3. Upload an index document.

Amazon S3 serves this index document whenever a user specifies the URL for the root of your website, or a subfolder. For example, when a customer requests

http://example-bucket.s3-website-us-east-1.amazonaws.com/, Amazon S3 returns the content of your index document at the root of the website,

http://example-bucket.s3-website-us-east-1.amazonaws.com/index.html.

Amazon Simple Storage Service Developer Guide Where Do I Go from Here?

a. Create a document.

The file name (index.html) must be same as the **Index Document Suffix** you provided when configuring your bucket as a website in the preceding steps.

b. Using the console, upload the index document to your bucket.

For information on uploading an object, go to Uploading Objects into Amazon S3.

4. Test your website.

a. Enter the following URL in the browser. Specify your bucket name and the region specific endpoint name (see Website Endpoints (p. 285)).

This is the URL to the root of your website. In response, Amazon S3 returns the index.html page you added to the bucket.

http://example-bucket.s3-website-region.amazonaws.com



Note

HTTPS access to the website is not supported.

You now have a website hosted on Amazon S3.

Where Do I Go from Here?

The preceding section provides you a step-by-step procedure to configure a bucket as a website using the AWS Management Console. This section outlines the key website features and where you can learn more about these features.

Website Endpoints

There are region-specific website endpoints available for accessing websites hosted on Amazon S3. It also describes how the website endpoint differs from the RESTAPI endpoint. For more information, see Website Endpoints (p. 285).

Configure Your Bucket as a Website

You can manage your website configuration using the AWS Management Console, any of the AWS SDKs, or a number of third party tools and libraries. For more information, see How Do I Configure My Bucket As a Website? (p. 290).

Index Document Support

Amazon S3 supports index documents at the root of the website as well as for subfolders. For more information, see Index Document Support (p. 287).

Custom Error Document Support

Should an error occur on the website endpoint, Amazon S3 returns an HTML error document. You can optionally provide a custom error document for Amazon S3 to return when any HTTP 4XX class response code occurs. For more information, see Custom Error Document Support (p. 288).

Website Endpoints

Topics

Key Differences Between the Amazon Website and the REST API Endpoint (p. 287)

Amazon Simple Storage Service Developer Guide Website Endpoints

When you configure a bucket as a website, the website is available via the region-specific website endpoint. The website endpoint you use must be in the same region that your bucket resides. These website endpoints are different than the REST API endpoints (see Request Endpoints (p. 12)). Amazon S3 supports the following website endpoint.

s3-website-region.amazonaws.com

The following table lists Amazon S3 regions and corresponding website endpoints.

Region	Website endpoint
US Standard	s3-website-us-east-1.amazonaws.com
US West (Northern California) Region	s3-website-us-west-1.amazonaws.com
EU (Ireland) Region	s3-website-eu-west-1.amazonaws.com
Asia Pacific (Singapore) Region	s3-website-ap-southeast-1.amazonaws.com
Asia Pacific (Tokyo) Region	s3-website-ap-northeast-1.amazonaws.com

In order for your customers to access content on the website endpoints, you must make all your content publicly readable. To make your content publicly readable, you can use a bucket policy or an objects ACL to grant these permissions.



Note

Requester Pays (see Requester Pays Buckets (p. 95)) or DevPay buckets do not allow access via the website endpoint. Any request to a bucket set up for Requester Pays or DevPay via the website endpoint will receive a 403 Access Denied response.

If your bucket, (i.e., example-bucket) resides in the US Standard region, the website is available at the following Amazon S3 website endpoint.

http://example-bucket.s3-website-us-east-1.amazonaws.com/

If you have a registered domain, you can add a DNS CNAME entry to point to the Amazon S3 website endpoint. For example, if you have registered domain, www.example-bucket.com, you could create a bucket www.example-bucket.com, and add a DNS CNAME entry pointing to

www.example-bucket.com.s3-website-<region>.amazonaws.com. All requests to
http://www.example-bucket.com will be routed to

www.example-bucket.com.s3-website-<region>.amazonaws.com. For more information, see Virtual Hosting of Buckets (p. 59).

Key Differences Between the Amazon Website and the REST API Endpoint

The website endpoint is optimized for access via a web browser. The following table describes the key differences between the Amazon REST API endpoint (see Request Endpoints (p. 12)) and the website endpoint.

Key Difference	REST API Endpoint	Website Endpoint
Requests supported	Supports all the bucket and object operations	Supports only GET and HEAD requests on objects.
Responses to GET and HEAD requests at the root of a bucket	Returns an XML listing the object keys in the bucket.	Returns the index document specified in the website configuration.
Error message handling	When a request to a REST API endpoint results in an error, Amazon S3 returns an XML error response.	When a request to a website endpoint results in an error, an HTML document is returned. However, you can optionally provide a custom error document when configuring a website, providing your customers with a more user-friendly experience. Amazon S3 will return this custom error document for any HTTP 4XX class of errors.
Access control	Supports both public and private content.	Supports only publicly readable content.

Index Document Support

An index document is a webpage that is returned when a request is made to the root of a website or any subfolder. For example, if a user enters http://www.example.com in the browser, the server returns http://www.example.com/index.html, where index.html is the default webpage of the website. Thus, your customers don't have to remember the exact URL to navigate to use for retrieving the default web page. When hosting your website on Amazon S3, you provide this index document name as part of configuring your bucket as a website, and an object with this name must exist in your bucket. The trailing slash at the root-level URL is optional. For example, if you configure your website with index.html as the index document, either of the following two URLs return the index.html index document at the root of your website.

```
http://example-bucket.s3-website-region.amazonaws.com/http://example-bucket.s3-website-region.amazonaws.com
```

Index Documents and Folders

Objects stored in Amazon S3 are stored within a flat container, i.e., an Amazon S3 bucket, and it does not provide any hierarchical organization, similar to a file system's. However, you can create a logical hierarchy using object key names and use these names to infer logical folders that contain these objects. For example, consider a bucket with three objects and the following key names.

sample1.jpg

Amazon Simple Storage Service Developer Guide Custom Error Document Support

photos/2006/Jan/sample2.jpg

photos/2006/Feb/sample3.jpg


All three objects are stored within a bucket, with no physical hierarchical organization. However, you can infer the following logical folder structure from the key names.

sample1.jpg object is at the root of the bucket

sample2.jpg object is in the photos/2006/Jan subfolder, and

sample3.jpg object is in photos/2006/Feb subfolder.

The AWS Management Console also supports the concept of folders, by using the same key naming convention used in the preceding sample. The following console screenshot shows an <code>ExampleBucket</code> with a <code>photos</code> folder. You can upload objects to the bucket or to the <code>photos</code> folder within the bucket. If you add the object <code>sample.jpg</code> to the bucket, the key name is <code>sample.jpg</code>. If you upload the object to the <code>photos</code> folder, the object key name is <code>photos/sample.jpg</code>.



If your keys follow the same naming convention described above, then Amazon S3 will return the content for your index document whenever it infers that your request is for a subfolder. You should have the index document at each level of your key's hierarchy. When a user specifies a URL that resembles a folder lookup, the presence or absence of a trailing slash determines the behavior of the website endpoint. For example, the following URL, with a trailing slash, returns the photos/index.html index document.

http://example-bucket.s3-website-region.amazonaws.com/photos/

However, if you exclude the trailing slash from the preceding URL, Amazon S3 first looks for an object photos in the bucket. If the photos object is not found, then it searches for an index document, photos/index.html. If found, Amazon S3 returns a 302 Found message and points to the photos/key. For subsequent requests to photos/, Amazon S3 returns the photos/index.html content. If the index document is also not found. Amazon S3 returns an error.

Custom Error Document Support

The following table lists the subset of HTTP response codes that Amazon S3 returns when an error occurs.

HTTP Error Code	Description
301 Moved Permanently	When a user sends a request directly to the Amazon S3 website endpoints (http://s3-website- <region>.amazonaws.com/), Amazon S3 returns a 301 Moved Permanently response and redirects those requests to http://aws.amazon.com/s3.</region>

Amazon Simple Storage Service Developer Guide Custom Error Document Support

HTTP Error Code	Description
302 Found	When Amazon S3 receives a request for a key x , http:// <bucket>.s3-website-<region>.amazonaws.com/x, without a trailing slash, it first looks for the object with the keyname x. If the object is not found, Amazon S3 determines that the request is for subfolder x and redirects the request by adding a slash at the end, and returns 302 Found.</region></bucket>
304 Not Modified	Amazon S3 users request headers If-Modified-Since, If-Unmodified-Since, If-Match and/or If-None-Match to determine whether the requested object is same as the cached copy held by the client. If the object is the same, the website endpoint returns a 304 Not Modified response.
400 Malformed Request	The website endpoint responds with a 400 Malformed Request when a user attempts to access a bucket through the incorrect regional endpoint.
403 Forbidden	The website endpoint responds with a 403 Forbidden when a user request translates to an object that is not publicly readable. The object owner must make the object publicly readable using a bucket policy or an ACL.
404 Not Found	 The website endpoint responds with 404 Not Found for the following reasons: Amazon S3 determines the website URL refers to an object key that does not exist Amazon infers the request is for an index document that does not exist A bucket specified in the URL does not exist A bucket specified in the URL exists, however, it is not configured as a website For information on how Amazon S3 interprets the URL as a request for an object or an index document, see Index Document Support (p. 287).
500 Service Error	The website endpoint responds with a 500 Service Error when an internal server error occurs.
503 Service Unavailable	The website endpoint responds with a 503 Service Unavailable when Amazon S3 determines that you need to reduce your request rate.

For each of these errors, Amazon S3 returns a predefined HTML as shown in the following sample HTML returned for **403 Forbidden** response.

403 Forbidden

- Code: AccessDenied
- Message: Access Denied
- RequestId: 873CA367A51F7EC7
- $\bullet \ \ HostId: DdQezl9vkuw5huD5HKsFaTDm9KH4PZzCPRkW3igimILbTu1DiYhXjgyd7pVxq32$

An Error Occurred While Attempting to Retrieve a Custom Error Document

- Code: AccessDenied
- Message: Access Denied

You can optionally provide a custom error document with a user-friendly error message and with additional help. You provide this custom error document as part of adding website configuration to your bucket. Amazon S3 returns your custom error document for only the HTTP 4XX class of error codes.

Error Documents and Browser Behavior

When an error occurs, Amazon S3 returns an HTML error document. If you have configured your website with a custom error document, Amazon S3 returns that error document. However, note that when an error occurs, some browsers display their own error message, ignoring the error document Amazon S3 returns. For example, when an HTTP 404 Not Found error occurs, Chrome might display its own error ignoring the error document that Amazon S3 returns.

How Do I Configure My Bucket As a Website?

You can host static websites in Amazon S3 by adding a website configuration to your bucket. You do this by adding the website configuration information to a bucket's website subresource. The only required configuration information is the index document name. You can optionally provide a custom error document name.

There are several ways you can add website configuration to your bucket. You can use the AWS Management Console, which provides a UI to manage website configuration without writing any code. You can use the AWS SDK for Java, PHP, and .NET to programmatically manage website configuration. The AWS SDK provides a wrapper API over the underlying REST API supported by Amazon S3. You can also use a variety of third party tools and libraries for managing your buckets website configuration.

For more information, see Managing Bucket Website Configuration (p. 86).

If a bucket is configured as a website, the website is accessible via the website endpoints. If you remove the website configuration, the bucket is still available using the REST API endpoint (see Request Endpoints (p. 12)).

Permissions Required for Website Access

When you configure a bucket as a website, you must make the objects you want to serve via the website endpoint publicly readable. You can accomplish this by writing a bucket policy granting everyone s3:GetObject permission. On the website endpoint, if users requests an object that does not exist, the website endpoint returns 404 (Not Found). However, if object exists but you have not granted read permission on the object, the website endpoint returns a 403 (Access Denied). This can allow a user to infer if specific objects exist in your bucket. If you do not want this behavior, you should not enable website support for your bucket.

The following sample bucket policy grants everyone access to the objects in the specified folder. For more information on bucket policies, see Using Bucket Policies (p. 216).

Amazon Simple Storage Service Developer Guide Permissions Required for Website Access

```
1
}
```

You can grant public read permission to your objects using either a bucket policy or an object ACL. To make an object publicly readable using an ACL, you grant READ permission to the AllUsers group as shown in the following grant element. You add this grant element to the object ACL. For more information on managing ACLs, see Using ACLs (p. 228).

Setting Up Notification of Bucket Events

The Amazon S3 notifications feature enables you to configure a bucket so that Amazon S3 publishes a message to an Amazon Simple Notification Service (SNS) topic when Amazon S3 detects a key event on a bucket. Subscribers to this topic can have messages for bucket events delivered to an endpoint such as a web server, e-mail address, or an Amazon Simple Queue Service queue.

Note that Notification fees will be charged at the normal Amazon SNS rates. For details about pricing, go to http://aws.amazon.com/sns/#pricing. There are no additional Amazon S3 charges for publishing a message to an Amazon SNS topic beyond the request fee to enable and disable the feature. In order to receive notifications of a bucket's events, you must subscribe to the topic that has been configured for that bucket.

Currently, the s3:ReducedRedundancyLostObject event is the only event supported by Amazon S3. The s3:ReducedRedundancyLostObject event is triggered when Amazon S3 detects that it has lost all replicas of a Reduced Redundancy Storage (RRS) object and can no longer service requests for that object. Notification on this event can enable you to replace missing RRS objects proactively to ensure there is no customer impact.

Notifications are published to a specified Amazon SNS topic. Currently, only one topic can be configured for notifications. If the bucket owner and Amazon SNS topic owner are the same, the bucket owner has permission to publish notifications to the topic by default. Otherwise, the owner of the topic must create a policy to enable the bucket owner to publish to the topic. For more information about creating this policy, see Example Cases for Amazon SNS Access Control.



Important

The Amazon SNS topic specified for a bucket's notification configuration must be in the same region as the bucket.

The following table lists the topic regions for the possible <code>LocationContraint</code> values for buckets.

LocationConstraint	Topic Region
Empty string	us-east-1
EU	eu-west-1

LocationConstraint	Topic Region
us-west-1	us-west-1
ap-southeast-1	ap-southeast-1

By default, only the bucket owner has permission to set and view the notifications on a bucket. However, the bucket owner can use a bucket policy to grant permission to other users to set this configuration using the s3:PutBucketNotification permission or view this configuration via the s3:GetBucketNotification permission. For more information about bucket policy, see Using Bucket Policies (p. 216).

Similar to other bucket settings, there is a sub-resource for each bucket enabling you to set or view that bucket's notification settings. To configure notifications on a bucket, use the bucket's notification sub-resource with the Amazon S3 REST API. For more information about the notification sub-resource, see Put Bucket notification and Get Bucket notification.

To set notifications for a bucket

• Use the PUT operation with a request body containing a NotificationConfiguration element that specifies the Amazon Resource Name (ARN) of the Amazon SNS topic, where the notification will be published, and what events will be reported.

After you call the PUT operation to configure notifications on a bucket, Amazon S3 publishes a test notification to ensure that the topic exists and that the bucket owner has permission to publish to the specified topic. If the notification is successfully published to the SNS topic, the PUT operation updates the bucket configuration and returns a 200 OK response with a x-amz-sns-test-message-id header containing the message ID of the test notification sent to the topic. For information about PUT operation errors, see Put Bucket notification.

The message published for an event to a topic contains the fields listed in the following table.

Name	Description
Service	Amazon S3.
Event	Currently, the only supported event is s3:ReducedRedundancyLostObject.
Time	The time that the event was triggered.
Bucket	The name of the bucket.

Name	Description
Key	The object name.
VersionId	If versioning is enabled, the version ID. If versioning is not enabled, empty string.
RequestID	A unique ID that identifies which Amazon S3 operation published the notification.
HostID	A unique ID that identifies which host sent the message.

The following message is an example of a message publishing an s3: ReducedRedundancyLostObject event:

```
{
    "Service":"Amazon S3",
    "Event": "s3:ReducedRedundancyLostObject",
    "Time":"2010-02-11T23:48:22.000Z",
    "Bucket": "myphotos",
    "Key": "Home/2009/10/carvingpumpkins.jpg",
    "VersionId":"qfXHy5689N7n9mWVwanN_hIroMn_rzXl",
    "RequestId":"4442587FB7D0A2F9",
    "HostId":"fHZOHz+oQlKAFQ7RgVSklvcDNYI0v05gsOWWeJcyTTXWgGzI6CC5FZVICjD9bUzT"
}
```

The following message is an example of the test message that Amazon S3 sends when a bucket is enabled for notifications:

```
{
    "Service":"Amazon S3",
    "Event": "s3:TestEvent",
    "Time":"2010-02-11T23:48:22.000Z",
    "Bucket": "myphotos",
    "RequestId":"4442587FB7D0A2F9",
    "HostId":"fHZOHz+oQlKAFQ7RgVSklvcDNYI0v05gsOWWeJcyTTXWgGzI6CC5FZVICjD9bUzT"
}
```

To read the notification configuration for a bucket

• Use the GET operation, which returns a <code>NotificationConfiguration</code> element containing the Amazon SNS topic and events set for notification on the bucket.

```
GET ?notification HTTP/1.1
Host: quotes.s3.amazonaws.com
Date: Wed, 09 June 2010 12:00:00 GMT
Authorization: AWS 15B4D3461F177624206A:xQE0diMbLRepdf3YB+FIEXAMPLE=
```

To turn off notifications on a bucket
• Use the PUT operation with a request body containing an empty NotificationConfiguration element.

Request Routing

Topics

- Request Redirection and the REST API (p. 296)
- DNS Considerations (p. 299)

Programs that make requests against buckets created using the <CreateBucketConfiguration> API must support redirects. Additionally, some clients that do not respect DNS TTLs might encounter issues.

This section describes routing and DNS issues to consider when designing your service or application for use with Amazon S3.

Request Redirection and the REST API

Overview

Amazon S3 uses the Domain Name System (DNS) to route requests to facilities that can process them. This system works very effectively. However, temporary routing errors can occur.

If a request arrives at the wrong Amazon S3 location, Amazon S3 responds with a temporary redirect that tells the requester to resend the request to a new endpoint.

If a request is incorrectly formed, Amazon S3 uses permanent redirects to provide direction on how to perform the request correctly.




Important

Every Amazon S3 program must be designed to handle redirect responses. The only exception is for programs that work exclusively with buckets that were created without <CreateBucketConfiguration>. For more information on location constraints, see Buckets and Regions (p. 84).

DNS Routing

DNS routing routes requests to appropriate Amazon S3 facilities.

The following figure shows an example of DNS routing.



The client makes a DNS request to get an object stored on Amazon S3.
 The client receives one or more IP addresses for facilities that can process the request.
 The client makes a request to Amazon S3 Facility B.
 Facility B returns a copy of the object.

Temporary Request Redirection

A temporary redirect is a type of error response that signals to the requester that he should resend his request to a different endpoint.

Due to the distributed nature of Amazon S3, requests can be temporarily routed to the wrong facility. This is most likely to occur immediately after buckets are created or deleted. For example, if you create a new bucket and immediately make a request to the bucket, you will receive a temporary redirect. After information about the bucket propagates through DNS, redirects will be rare.


Temporary redirects contain a URI to the correct facility which you can use to immediately resend the request.



Important

Do not reuse an endpoint provided by a previous redirect response. It might appear to work (even for long periods of time), but might provide unpredictable results and will eventually fail without notice.

The following figure shows an example of a temporary redirect.



1	The client makes a DNS request to get an object stored on Amazon S3.
2	The client receives one or more IP addresses for facilities that can process the request.
3	The client makes a request to Amazon S3 Facility B.
4	Facility B returns a redirect indicating the object is available from Location C.
5	The client resends the request to Facility C.
6	Facility C returns a copy of the object.

Permanent Request Redirection

A permanent redirect indicates that your request addressed a resource inappropriately. For example, permanent redirects occur if you use a path-style request to access a bucket that was created using <CreateBucketConfiguration>. For more information, see Using CreateBucketConfiguration (p. 84).

To help you find these errors during development, this type of redirect does not contain a Location HTTP header that allows you to automatically follow the request to the correct location. Consult the resulting XML error document for help using the correct Amazon S3 endpoint.

Example REST API Redirect

Example SOAP API Redirect

```
<soapenv:Body>
  <soapenv:Fault>
      <Faultcode>soapenv:Client.TemporaryRedirect</Faultcode>
      <Faultstring>Please re-send this request to the specified temporary endpoint.

      Continue to use the original request endpoint for future requests.</Fault string>
      <Detail>
            <Bucket>images</Bucket>
            <Endpoint>s3-gztb4pa9sq.amazonaws.com</Endpoint>
            </Detail>
            </soapenv:Fault>
      </soapenv:Body>
```

DNS Considerations

One of the design requirements of Amazon S3 is extremely high availability. One of the ways we meet this requirement is by updating the IP addresses associated with the Amazon S3 endpoint in DNS as needed. These changes are automatically reflected in short-lived clients, but not in some long-lived clients. Long-lived clients will need to take special action to re-resolve the Amazon S3 endpoint periodically to benefit from these changes. For more information about virtual machines (VMs), refer to the following:

- For Java, Sun's JVM caches DNS lookups forever by default; go to the "InetAddress Caching" section of the InetAddress documentation for information on how to change this behavior.
- For PHP, the persistent PHP VM that runs in the most popular deployment configurations caches DNS lookups until the VM is restarted. Go to the getHostByName PHP docs.

Performance Optimization

Topics

- TCP Window Scaling (p. 300)
- TCP Selective Acknowledgement (p. 300)

Amazon S3 provides new features that support high performance networking. These include TCP window scaling and selective acknowledgements.



Note

For more information on high performance tuning, go to http://-www.psc.edu/-networking/-projects/-tcptune/.

TCP Window Scaling

TCP window scaling allows you to improve network throughput performance between your operating system and application layer and Amazon S3 by supporting window sizes larger than 64 KB. At the start of the TCP session, a client advertises its supported receive window WSCALE factor, and Amazon S3 responds with its supported receive window WSCALE factor for the upstream direction.

Although TCP window scaling can improve performance, it can be challenging to set correctly. Make sure to adjust settings at both the application and kernel level. For more information about TCP window scaling, refer to your operating system's documentation and go to RFC 1323.

TCP Selective Acknowledgement

TCP selective acknowledgement is designed to increase recovery time after a large number of packet losses. TCP selective acknowledgement is supported by most newer operating systems, but might have to be enabled. For more information about TCP selective acknowledgements, refer to the documentation that accompanied your operating system and go to RFC 2018.

Using BitTorrent with Amazon S3

Topics

- How You are Charged for BitTorrent Delivery (p. 301)
- Using BitTorrent to Retrieve Objects Stored in Amazon S3 (p. 302)
- Publishing Content Using Amazon S3 and BitTorrent (p. 303)

BitTorrent™ is an open, peer-to-peer protocol for distributing files. You can use the BitTorrent protocol to retrieve any publicly-accessible object in Amazon S3. This section describes why you might want to use BitTorrent to distribute your data out of Amazon S3 and how to do so.

Amazon S3 supports the BitTorrent protocol so that developers can save costs when distributing content at high scale. Amazon S3 is useful for simple, reliable storage of any data. The default distribution mechanism for Amazon S3 data is via client/server download. In client/server distribution, the entire object is transferred point-to-point from Amazon S3 to every authorized user who requests that object. While client/server delivery is appropriate for a wide variety of use cases, it is not optimal for everybody. Specifically, the costs of client/server distribution increase linearly as the number of users downloading objects increases. This can make it expensive to distribute popular objects.

BitTorrent addresses this problem by recruiting the very clients that are downloading the object as distributors themselves: Each client downloads some pieces of the object from Amazon S3 and some from other clients, while simultaneously uploading pieces of the same object to other interested "peers." The benefit for publishers is that for large, popular files the amount of data actually supplied by Amazon S3 can be substantially lower than what it would have been serving the same clients via client/server download. Less data transferred means lower costs for the publisher of the object.



Note

You can get torrent only for objects that are less than 5 GB in size.

How You are Charged for BitTorrent Delivery

There is no extra charge for use of BitTorrent with Amazon S3. Data transfer via the BitTorrent protocol is metered at the same rate as client/server delivery. To be precise, whenever a downloading BitTorrent client requests a "piece" of an object from the Amazon S3 "seeder," charges accrue just as if an anonymous request for that piece had been made using the REST or SOAP protocol. These charges will appear on your Amazon S3 bill and usage reports in the same way. The difference is that if a lot of clients are requesting the same object simultaneously via BitTorrent, then the amount of data Amazon S3 must serve

S3

to satisfy those clients will be lower than with client/server delivery. This is because the BitTorrent clients are simultaneously uploading and downloading amongst themselves.

The data transfer savings achieved from use of BitTorrent can vary widely depending on how popular your object is. Less popular objects require heavier use of the "seeder" to serve clients, and thus the difference between BitTorrent distribution costs and client/server distribution costs might be small for such objects. In particular, if only one client is ever downloading a particular object at a time, the cost of BitTorrent delivery will be the same as direct download.

Using BitTorrent to Retrieve Objects Stored in Amazon S3

Any object in Amazon S3 that can be read anonymously can also be downloaded via BitTorrent. Doing so requires use of a BitTorrent client application. Amazon does not distribute a BitTorrent client application, but there are many free clients available. The Amazon S3BitTorrent implementation has been tested to work with the official BitTorrent client (go to https://www.bittorrent.com/).

The starting point for a BitTorrent download is a .torrent file. This small file describes for BitTorrent clients both the data to be downloaded and where to get started finding that data. A .torrent file is a small fraction of the size of the actual object to be downloaded. Once you feed your BitTorrent client application an Amazon S3 generated .torrent file, it should start downloading immediately from Amazon S3 <code>and</code> from any "peer" BitTorrent clients.

Retrieving a .torrent file for any publicly available object is easy. Simply add a "?torrent" query string parameter at the end of the REST GET request for the object. No authentication is required. Once you have a BitTorrent client installed, downloading an object using BitTorrent download might be as easy as opening this URL in your web browser.

There is no mechanism to fetch the .torrent for an Amazon S3 object using the SOAP API.

Example

This example retrieves the Torrent file for the "Nelson" object in the "quotes" bucket.

Sample Request

```
GET /quotes/Nelson?torrent HTTP/1.0
Date: Wed, 25 Nov 2009 12:00:00 GMT
```

Sample Response

```
HTTP/1.1 200 OK
x-amz-request-id: 7CD745EBB7AB5ED9
Date: Wed, 25 Nov 2009 12:00:00 GMT
Content-Disposition: attachment; filename=Nelson.torrent;
Content-Type: application/x-bittorrent
Content-Length: 537
Server: AmazonS3
<br/>
<
```

Publishing Content Using Amazon S3 and BitTorrent

Every anonymously readable object stored in Amazon S3 is automatically available for download using BitTorrent. The process for changing the ACL on an object to allow anonymous READ operations is described in Access Control (p. 204).

You can direct your clients to your BitTorrent accessible objects by giving them the .torrent file directly or by publishing a link to the ?torrent URL of your object. One important thing to note is that the .torrent file describing an Amazon S3 object is generated on-demand, the first time it is requested (via the REST ?torrent resource). Generating the .torrent for an object takes time proportional to the size of that object. For large objects, this time can be significant. Therefore, before publishing a ?torrent link, we suggest making the first request for it yourself. Amazon S3 might take several minutes to respond to this first request, as it generates the .torrent file. Unless you update the object in question, subsequent requests for the .torrent will be fast. Following this procedure before distributing a ?torrent link will ensure a smooth BitTorrent downloading experience for your customers.

To stop distributing a file using BitTorrent, simply remove anonymous access to it. This can be accomplished by either deleting the file from Amazon S3, or modifying your access control policy to prohibit anonymous reads. After doing so, Amazon S3 will no longer act as a "seeder" in the BitTorrent network for your file, and will no longer serve the .torrent file via the ?torrent REST API. However, after a .torrent for your file is published, this action might not stop public downloads of your object that happen exclusively using the BitTorrent peer to peer network.

Using Amazon DevPay with Amazon S3

Topics

- Amazon S3 Customer Data Isolation (p. 304)
- Amazon DevPay Token Mechanism (p. 305)
- Amazon S3 and Amazon DevPay Authentication (p. 305)
- Amazon S3 Bucket Limitation (p. 306)
- Amazon S3 and Amazon DevPay Process (p. 306)
- Additional Information (p. 307)

Amazon DevPay enables you to charge customers for using your Amazon S3 product through Amazon's authentication and billing infrastructure. You can charge any amount for your product including usage charges (storage, transactions, and bandwidth), monthly fixed charges, and a one-time charge.

Once a month, Amazon bills your customers for you. AWS then deducts the fixed Amazon DevPay transaction fee and pays you the difference. AWS then separately charges you for the Amazon S3 usage costs incurred by your customers and the percentage-based Amazon DevPay fee.

If your customers do not pay their bills, AWS turns off access to Amazon S3 (and your product). AWS handles all payment processing.

Amazon S3 Customer Data Isolation


Amazon DevPay requests store and access data on behalf of the users of your product. The resources created by your application are owned by your users; unless you modify the ACL, you cannot read or modify the user's data.

Data stored by your product is isolated from other Amazon DevPay products and general Amazon S3 access. Customers that *store* data in Amazon S3 through your product can only *access* that data through your product. The data cannot be accessed through other Amazon DevPay products or through a personal AWS account.

Two users of a product can only access each other's data if your application explicitly grants access through the ACL.

Example

The following figure illustrates allowed, disallowed, and conditional (discretionary) data access.



Betty's access is limited as follows:

- She can access Lolcatz data through the Lolcatz product. If she attempts to access her Lolcatz data through another product or a personal AWS account, her requests will be denied.
- She can access Alvin's eScrapBook data through the eScrapBook product if access is explicitly granted.

Amazon DevPay Token Mechanism

To enable you to make requests on behalf of your customers and ensure that your customers are billed for use of your application, your application must send two tokens with each request: the product token and the user token.

The product token identifies your product; you must have one product token for each Amazon DevPay product that you provide. The user token identifies a user in relationship to your product; you must have a user token for each user/product combination. For example, if you provide two products and a user subscribes to each, you must obtain a separate user token for each product.

For information on obtaining product and user tokens, refer to the Amazon DevPay Developer Guide.

Amazon S3 and Amazon DevPay Authentication


Although the token mechanism uniquely identifies a customer and product, it does not provide authentication.


Normally, your applications communicate directly with Amazon S3 using your Access Key ID and Secret Access Key. For Amazon DevPay, Amazon S3 authentication works a little differently.

If your Amazon DevPay product is a web application, you securely store the Secret Access Key on your servers and use the user token to specify the customer for which requests are being made.

However, if your Amazon S3 application is installed on your customers' computers, your application must obtain an Access Key ID and a Secret Access Key for each installation and must use those credentials when communicating with Amazon S3.

The following figure shows the differences between authentication for web applications and user applications.





Amazon S3 Bucket Limitation

Each of your customers can have up to 100 buckets for each Amazon DevPay product that you sell. For example, if a customer uses three of your products, the customer can have up to 300 buckets (100 * 3) plus any buckets outside of your Amazon DevPay products (i.e., buckets in Amazon DevPay products from other developers and the customer's personal AWS account).

Amazon S3 and Amazon DevPay Process

Following is a high-level overview of the Amazon DevPay process.

Launch Process

A customer signs up for your product through Amazon.
The customer receives an activation key.
The customer enters the activation key into your application.
Your application communicates with Amazon and obtains the user's token. If your application is installed on the user's computer, it also obtains an Access Key ID and Secret Access Key on behalf of the customer.
Your application provides the customer's token and the application product token when making Amazon S3 requests on behalf of the customer. If your application is installed on the customer's computer, it authenticates with the customer's credentials.
Amazon uses the customer's token and your product token to determine who to bill for the Amazon S3 usage.
Once a month, Amazon processes usage data and bills your customers according to the terms you defined.

Amazon Simple Storage Service Developer Guide Additional Information

AWS deducts the fixed Amazon DevPay transaction fee and pays you the difference. AWS then separately charges you for the Amazon S3 usage costs incurred by your customers and the percentage-based Amazon DevPay fee.

Additional Information

For information about using, setting up, and integrating with Amazon DevPay, refer to the *Amazon DevPay Developer Guide*.

Handling Errors

Topics

- The REST Error Response (p. 308)
- The SOAP Error Response (p. 309)
- Amazon S3 Error Best Practices (p. 310)

This section describes REST and SOAP errors and how to handle them.

The REST Error Response

Topics

- Response Headers (p. 309)
- Error Response (p. 309)

If a REST request results in an error, the HTTP reply has:

- · An XML error document as the response body
- Content-Type: application/xml
- An appropriate 3xx, 4xx, or 5xx HTTP status code

Following is an example of a REST Error Response.

For more information about Amazon S3 errors, go to ErrorCodeList.

Response Headers

Following are response headers returned by all operations:

- x-amz-request-id: A unique ID assigned to each request by the system. In the unlikely event that you have problems with Amazon S3, Amazon can use this to help troubleshoot the problem.
- x-amz-id-2: A special token that will help us to troubleshoot problems.

Error Response

Topics

- Error Code (p. 309)
- Error Message (p. 309)
- Further Details (p. 309)

When an Amazon S3 request is in error, the client receives an error response. The exact format of the error response is API specific: For example, the REST error response differs from the SOAP error response. However, all error responses have common elements.

Error Code

The error code is a string that uniquely identifies an error condition. It is meant to be read and understood by programs that detect and handle errors by type. Many error codes are common across SOAP and REST APIs, but some are API-specific. For example, NoSuchKey is universal, but UnexpectedContent can occur only in response to an invalid REST request. In all cases, SOAP fault codes carry a prefix as indicated in the table of error codes, so that a NoSuchKey error is actually returned in SOAP as Client.NoSuchKey.

Error Message

The error message contains a generic description of the error condition in English. It is intended for a human audience. Simple programs display the message directly to the end user if they encounter an error condition they don't know how or don't care to handle. Sophisticated programs with more exhaustive error handling and proper internationalization are more likely to ignore the error message.

Further Details

Many error responses contain additional structured data meant to be read and understood by a developer diagnosing programming errors. For example, if you send a Content-MD5 header with a REST PUT request that doesn't match the digest calculated on the server, you receive a BadDigest error. The error response also includes as detail elements the digest we calculated, and the digest you told us to expect. During development, you can use this information to diagnose the error. In production, a well-behaved program might include this information in its error log.

The SOAP Error Response

In SOAP, an error result is returned to the client as a SOAP fault, with the HTTP response code 500. If you do not receive a SOAP fault, then your request was successful. The Amazon S3 SOAP fault code is comprised of a standard SOAP 1.1 fault code (either "Server" or "Client") concatenated with the Amazon S3-specific error code. For example: "Server.InternalError" or "Client.NoSuchBucket". The SOAP fault

Amazon Simple Storage Service Developer Guide Amazon S3 Error Best Practices

string element contains a generic, human readable error message in English. Finally, the SOAP fault detail element contains miscellaneous information relevant to the error.

For example, if you attempt to delete the object "Fred", which does not exist, the body of the SOAP response contains a "NoSuchKey" SOAP fault.

Example

```
<soapenv:Body>
  <soapenv:Fault>
    <Faultcode>soapenv:Client.NoSuchKey</Faultcode>
    <Faultstring>The specified key does not exist.</Faultstring>
    <Detail>
        <Key>Fred</Key>
        </Detail>
        </soapenv:Fault>
</soapenv:Body>
```

For more information about the errors, go to ErrorCodeList.

Amazon S3 Error Best Practices

When designing an application for use with Amazon S3, it is important to handle Amazon S3 errors appropriately. This section describes issues to consider when designing your application.

Retry InternalErrors

Internal errors are errors that occur within the Amazon S3 environment.

Requests that receive an InternalError response might not have processed. For example, if a PUT request returns InternalError, a subsequent GET might retrieve the old value or the updated value.

If Amazon S3 returns an InternalError response, retry the request.

Tune Application for Repeated SlowDown errors

As with any distributed system, S3 has protection mechanisms which detect intentional or unintentional resource over-consumption and react accordingly. SlowDown errors can occur when a high request rate triggers one of these mechanisms. Reducing your request rate will decrease or eliminate errors of this type. Generally speaking, most users will not experience these errors regularly; however, if you would like more information or are experiencing high or unexpected SlowDown errors, please post to our Amazon S3 developer forum http://developer.amazonwebservices.com/connect/forum.jspa?forumID=24 or sign up for AWS Premium Support http://aws.amazon.com/premiumsupport/.

Isolate Errors

Amazon S3 provides a set of error codes that are used by both the SOAP and REST API. The SOAP API returns standard Amazon S3 error codes. The REST API is designed to look like a standard HTTP server and interact with existing HTTP clients (e.g., browsers, HTTP client libraries, proxies, caches, and so on). To ensure the HTTP clients handle errors properly, we map each Amazon S3 error to an HTTP status code.

Amazon Simple Storage Service Developer Guide Isolate Errors

HTTP status codes are less expressive than Amazon S3 error codes and contain less information about the error. For example, the NoSuchKey and NoSuchBucket Amazon S3 errors both map to the HTTP 404 Not Found status code.

Although the HTTP status codes contain less information about the error, clients that understand HTTP, but not the Amazon S3 API, will usually handle the error correctly.

Therefore, when handling errors or reporting Amazon S3 errors to end users, use the Amazon S3 error code instead of the HTTP status code as it contains the most information about the error. Additionally, when debugging your application, you should also consult the human readable <Details> element of the XML error response.

Server Access Logging

Topics

- Server Access Logging Configuration API (p. 313)
- Delivery of Server Access Logs (p. 315)
- Server Access Log Format (p. 316)
- Setting Up Server Access Logging (p. 320)



Important

This section describes Beta functionality that is subject to change in future releases. Please provide feedback on this functionality in the Amazon S3 Developer Forum.

An Amazon S3 bucket can be configured to create access log records for the requests made against it. An access log record contains details about the request such as the request type, the resource with which the request worked, and the time and date that the request was processed. Server access logs are useful for many applications, because they give bucket owners insight into the nature of requests made by clients not under their control.

By default, server access logs are not collected for a bucket. To learn how to enable server access logging, see Server Access Logging Configuration API (p. 313).

Once logging is enabled for a bucket, available log records are periodically aggregated into log files and delivered to you via an Amazon S3 bucket of your choosing. For a detailed description of this process, see Delivery of Server Access Logs (p. 315).

For information on how to interpret the contents of log files, see Server Access Log Format (p. 316).

To walk through the process of enabling logging for your bucket, see Setting Up Server Access Logging (p. 320).



Note

There is no extra charge for enabling the server access logging feature on an Amazon S3 bucket, however any log files the system delivers to you will accrue the usual charges for storage (you can delete the log files at any time). No data transfer charges will be assessed for log file delivery, but access to the delivered log files is charged for data transfer in the usual way.

Server Access Logging Configuration API



Important

This section describes Beta functionality that is subject to change in future releases. Please provide feedback on this functionality in the Amazon S3 Developer Forum.

Each Amazon S3 bucket has an associated XML sub-resource that you can read and write in order to inspect or change the logging status for that bucket. The XML schema for the bucket logging status resource is common across SOAP and REST.

The BucketLoggingStatus element has the following structure.

Example

```
<?xml version="1.0" encoding="UTF-8"?>
<BucketLoggingStatus xmlns="http://doc.s3.amazonaws.com/2006-03-01">
   <LoggingEnabled>
        <TargetBucket>mylogs</TargetBucket>
        <TargetPrefix>access_log-</TargetPrefix>
        <TargetGrants>
     <Grant>
        <Grantee xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"</pre>
xsi:type="AmazonCustomerByEmail">
             <EmailAddress>email_address/EmailAddress>
        </Grantee>
        <Permission>permission
     </Grant>
        </TargetGrants>
   </LoggingEnabled>
</BucketLoggingStatus>
```

Following is a list of elements that belong to the BucketLoggingStatus element.

• LoggingEnabled

The presence of this element indicates that server access logging is enabled for the bucket. The absence of this element (and all nested elements) indicates that logging is disabled for the bucket.

• TargetBucket

This element specifies the bucket where server access logs will be delivered. You can have your logs delivered to any bucket that you own, including the same bucket that is being logged. You can also configure multiple buckets to deliver their logs to the same target bucket. In this case you should choose a different TargetPrefix for each source bucket so that the delivered log files can be distinguished by key.



Note

The source and the target buckets must be in the same location. For more information about bucket location constraints, see Buckets and Regions (p. 84)

• TargetPrefix

Amazon Simple Storage Service Developer Guide Server Access Logging Configuration API

This element lets you specify a prefix for the keys that the delivered log files will be stored under. For information on how the key name for log files is constructed, see Delivery of Server Access Logs (p. 315).

• TargetGrants

The bucket owner is automatically granted FULL_CONTROL to all logs delivered to the bucket. This optional element enables you grant access to others. Any specified TargetGrants are added to the default ACL. For more information about ACLs, see Access Control Lists (p. 7).

To enable server access logging, Set or PUT a BucketLoggingStatus with a nested LoggingEnabled element. To disable server access logging, Set or PUT an empty BucketLoggingStatus element.

In REST, the address of the BucketLoggingStatus resource for a bucket 'mybucket' is http://s3.amazonaws.com/mybucket?logging.The PUT and GET methods are valid for this resource. For example, the following request fetches the BucketLoggingStatus resource for mybucket.

```
GET ?logging HTTP/1.1
Host: mybucket.s3.amazonaws.com
Date: Wed, 25 Nov 2009 12:00:00 GMT
Authorization: AWS YOUR_AWS_ACCESS_KEY_ID:YOUR_SIGNATURE_HERE
HTTP/1.1 200 OK
Date: Wed, 25 Nov 2009 12:00:00 GMT
Connection: close
Server: AmazonS3
<?xml version="1.0" encoding="UTF-8"?>
<BucketLoggingStatus xmlns="http://doc.s3.amazonaws.com/2006-03-01">
  <LoggingEnabled>
    <TargetBucket>mybucketlogs</TargetBucket>
    <TargetPrefix>mybucket-access_log-/</TargetPrefix>
        <TargetGrants>
     <Grant>
         <Grantee xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"</pre>
xsi:type="AmazonCustomerByEmail">
             <EmailAddress>user@company.com</EmailAddress>
         </Grantee>
         <Permission>READ</Permission>
     </Grant>
        </TargetGrants>
  </LoggingEnabled>
</BucketLoggingStatus>
```

In SOAP, you can work with BucketLoggingStatus resource using the SOAPSetBucketLoggingStatus and SOAPGetBucketLoggingStatus operations.

Amazon S3 checks the validity of the proposed BucketLoggingStatus when you try to Set or PUT to it. If the TargetBucket does not exist, is not owned by you, or does not have the appropriate grants, you will receive the InvalidTargetBucketForLogging error. If your proposed BucketLoggingStatus document is not well-formed XML or does not match our published schema, you will receive the MalformedXMLError.

BucketLoggingStatus Changes Take Effect Over Time

Changes to the logging status for a bucket are visible in the configuration API immediately, but they take time to actually affect the delivery of log files. For example, if you enable logging for a bucket, some requests made in the following hour might be logged, while others might not. Or, if you change the target bucket for logging from bucket A to bucket B, some logs for the next hour might continue to be delivered to bucket A, while others might be delivered to the new target bucket B. In all cases, the new settings will eventually take effect without any further action on your part.

Delivery of Server Access Logs



Important

This section describes Beta functionality that is subject to change in future releases. Please provide feedback on this functionality in the Amazon S3 Developer Forum.

Server access logs are written to the bucket of your choice, which can be the bucket from which the logs originate or a different bucket. If you choose a different bucket, it must have the same owner as the source bucket. Otherwise, no logs will be delivered.



Note

The source and the target buckets must be in the same location. For more information about bucket location constraints, see Buckets and Regions (p. 84).

When a log file is delivered to the target bucket, it is stored under a key in the following format.

TargetPrefixYYYY-mm-DD-HH-MM-SS-UniqueString

In the key, YYYY, mm, DD, HH, MM and SS are the digits of the year, month, day, hour, minute, and seconds (respectively) when the log file was delivered.

A log file delivered at a specific time can contain records written at any point before that time. There is no way to know whether all log records for a certain time interval have been delivered or not.

The TargetPrefix component of the key is a string provided by the bucket owner using the logging configuration API. For more information, see Server Access Logging Configuration API (p. 313).

The UniqueString component of the key carries no meaning and should be ignored by log processing software.

The system does not delete old log files. If you do not want server logs to accumulate, you must delete them yourself. To do so, use the List operation with the prefix parameter to locate old logs to delete. For more information, see Listing Object Keys (p. 193).

Access Control Interaction

Log files will be written to the target bucket under the identity of a member of the http://acs.amazonaws.com/groups/s3/LogDelivery group. These writes are subject to the usual access control restrictions. Therefore, logs will not be delivered unless the access control policy of the target bucket grants the log delivery group WRITE access. To ensure log files are delivered correctly, the log delivery group must also have READ_ACP permission on the target bucket. For more information about access control lists and groups, see Access Control (p. 204). For more information about correctly configuring your target bucket's access control policy, see the Setting Up Server Access Logging (p. 320).

Log files created in the target bucket have an access control list entry that consists of a FULL_CONTROL grant to the bucket owner and grants to any users specified through the TargetGrants element.

Best Effort Server Log Delivery

The server access logging feature is designed for best effort. You can expect that most requests against a bucket that is properly configured for logging will result in a delivered log record, and that most log records will be delivered within a few hours of the time that they were recorded.

However, the server logging feature is offered on a best-effort basis. The completeness and timeliness of server logging is not guaranteed. The log record for a particular request might be delivered long after the request was actually processed, or it might not be delivered at all. The purpose of server logs is to give the bucket owner an idea of the nature of traffic against his or her bucket. It is not meant to be a complete accounting of all requests.

Usage Report Consistency

It follows from the best-effort nature of the server logging feature that the usage reports available at the AWS portal might include usage that does not correspond to any request in a delivered server log.

Server Access Log Format



Important

This section describes Beta functionality that is subject to change in future releases. Please provide feedback on this functionality in the Amazon S3 Developer Forum.

The log files consist of a sequence of new-line delimited log records. Log records appear in no particular order. Each log record represents one request and consists of space delimited fields described in the following table.

Fi	eld Name	Example Entry	Notes	
1 1	ucket wner	314159b66967d86f031c7249d1d9a8024	The canonical user id of the owner of the source bucket.	
		9109428335cd0ef1cdc487b4566cb1b		

Amazon Simple Storage Service Developer Guide Server Access Log Format

Field Name	Example Entry	Notes
Bucket	mybucket	The name of the bucket that the request was processed against. If the system receives a malformed request and cannot determine the bucket, the request will not appear in any server access log.
Time	[04/Aug/2006:22:34:02 +0000]	The time at which the request was received. The format, using strftime() terminology, is [%d/%B/%Y:%H:%M:%S %z]
Remote IP	72.21.206.5	The apparent Internet address of the requester. Intermediate proxies and firewalls might obscure the actual address of the machine making the request.
Requester	314159b66967d86f031c7249d1d9a80 249109428335cd0ef1cdc487b4566cb1b	The canonical user id of the requester, or the string "Anonymous" for unauthenticated requests. This identifier is the same one used for access control purposes.
Request ID	3E57427F33A59F07	The request ID is a string generated by Amazon S3 to uniquely identify each request.
Operation	SOAP.CreateBucket or REST.PUT.OBJECT	Either SOAP.operation Or REST.HTTP_method.resource_type
Key	/photos/2006/08/puppy.jpg	The "key" part of the request, URL encoded, or "-" if the operation does not take a key parameter.
Request-URI	"GET /mybucket/photos/2006/08/ puppy.jpg?x-foo=bar"	The Request-URI part of the HTTP request message.
HTTP status	200	The numeric HTTP status code of the response.
Error Code	NoSuchBucket	The Amazon S3 Error Code (p. 309), or "-" if no error occurred.

Amazon Simple Storage Service Developer Guide Custom Access Log Information

Field Name	Example Entry	Notes
Bytes Sent	2662992	The number of response bytes sent, excluding HTTP protocol overhead, or "-" if zero.
Object Size	3462992	The total size of the object in question.
Total Time	70	The number of milliseconds the request was in flight from the server's perspective. This value is measured from the time your request is received to the time that the last byte of the response is sent. Measurements made from the client's perspective might be longer due to network latency.
Turn-Around Time	10	The number of milliseconds that Amazon S3 spent processing your request. This value is measured from the time the last byte of your request was received until the time the first byte of the response was sent.
Referrer	"http://www.amazon.com/webservices"	The value of the HTTP Referrer header, if present. HTTP user-agents (e.g. browsers) typically set this header to the URL of the linking or embedding page when making a request.
User-Agent	"curl/7.15.1"	The value of the HTTP User-Agent header.
Version Id	3HL4kqtJvjVBH40Nrjfkd	The version ID in the request, or "-" if the operation does not take a versionId parameter.

Any field can be set to "-" to indicate that the data was unknown or unavailable, or that the field was not applicable to this request.

Custom Access Log Information

You can include custom information to be stored in the access log record for a request by adding a custom query-string parameter to the URL for the request. Amazon S3 will ignore query-string parameters that begin with "x-", but will include those parameters in the access log record for the request, as part of the Request-URI field of the log record. For example, a GET request for

"s3.amazonaws.com/mybucket/photos/2006/08/puppy.jpg?x-user=johndoe" will work the same as the same request for "s3.amazonaws.com/mybucket/photos/2006/08/puppy.jpg", except that the

"x-user=johndoe" string will be included in the Request-URI field for the associated log record. This functionality is available in the REST interface only.

Extensible Server Access Log Format

From time to time, we might extend the access log record format by adding new fields to the end of each line. Code that parses server access logs must be written to handle trailing fields that it does not understand.

Additional Logging for Copy Operations

A copy operation involves a GET and a PUT. For that reason, we log two records when performing a copy operation. The previous table describes the fields related to the PUT part of the operation. The following table describes the fields in the record that relate to the GET part of the copy operation.

Field Name	Example Entry	Notes
Bucket Owner	314159b66967d86f031c7249d1d9a8024 9109428335cd0ef1cdc487b4566cb1b	The owner of the bucket that stores the object being copied.
Bucket	mybucket	The name of the bucket that stores the object being copied.
Time	[04/Aug/2006:22:34:02 +0000]	The time at which the request was received. The format, using strftime() terminology, is [%d/%B/%Y:%H:%M:%S %z]
Remote IP	72.21.206.5	The apparent Internet address of the requester. Intermediate proxies and firewalls might obscure the actual address of the machine making the request.
Requester	314159b66967d86f031c7249d1d9a80 249109428335cd0ef1cdc487b4566cb1b	The canonical user id of the requester, or the string "Anonymous" for unauthenticated requests. This identifier is the same one used for access control purposes.
Request ID	3E57427F33A59F07	The request ID is a string generated by Amazon S3 to uniquely identify each request.
Operation	REST.COPY.OBJECT_GET	Either SOAP.operation Or REST.HTTP_method.resource_type
Key	/photos/2006/08/puppy.jpg	The "key" of the object being copied or "-" if the operation does not take a key parameter.
Request-URI	"GET /mybucket/photos/2006/08/ puppy.jpg?x-foo=bar"	The Request-URI part of the HTTP request message.

Field Name	Example Entry	Notes
HTTP status	200	The numeric HTTP status code of the GET portion of the copy operation.
Error Code	NoSuchBucket	The Amazon S3 Error Code (p. 309), of the GET portion of the copy operation or "-" if no error occurred.
Bytes Sent	2662992	The number of response bytes sent, excluding HTTP protocol overhead, or "-" if zero.
Object Size	3462992	The total size of the object in question.
Total Time	70	The number of milliseconds the request was in flight from the server's perspective. This value is measured from the time your request is received to the time that the last byte of the response is sent. Measurements made from the client's perspective might be longer due to network latency.
Turn-Around Time	10	The number of milliseconds that Amazon S3 spent processing your request. This value is measured from the time the last byte of your request was received until the time the first byte of the response was sent.
Referrer	"http://www.amazon.com/webservices"	The value of the HTTP Referrer header, if present. HTTP user-agents (e.g. browsers) typically set this header to the URL of the linking or embedding page when making a request.
User-Agent	"curl/7.15.1"	The value of the HTTP User-Agent header.
Version Id	3HL4kqtJvjVBH40Nrjfkd	The version ID of the object being copied or "-" if the x-amz-copy-source header didn't specify a <code>versionId</code> parameter as part of the copy source.

Setting Up Server Access Logging



Important

This section describes Beta functionality that is subject to change in future releases. Please provide feedback on this functionality in the Amazon S3 Developer Forum.

Amazon Simple Storage Service Developer Guide Preparing the Target Bucket

The Amazon S3 server access logging feature lets you generate access log files for buckets that you own. These log files are delivered to you by writing them into a (possibly different) bucket that you own. Once delivered, the access logs are ordinary objects that you can read, list or delete at your convenience.

These instructions assume that you want to enable server access logging on one of your pre-existing buckets, and that you want to have those logs delivered into a new bucket you will create just for logging. We suppose that the bucket you want to log access to is called 'mybucket' and the new bucket you will create to hold your access logs is called 'mylogs'. This makes 'mybucket' the source bucket for logging and 'mylogs' the target bucket for logging. Whenever you see 'mybucket' or 'mylogs' in the example, replace them with the name of your bucket that you want to log, and the bucket you want to store your access logs, respectively.

This tutorial makes use of s3curl (go to s3curl.pl sample program) to work with the Amazon S3 REST API. Make sure you use the most recent version of s3curl, as it has been updated to support this tutorial. After invoking s3curl, always check for a 200 OK HTTP response. If you get some other response code, refer to the XML error response which likely contains information about what went wrong.

Preparing the Target Bucket

To prepare the target bucket

1. First, decide if you want your logs delivered to an existing bucket, or if you want to create a new bucket just for access log files. Following is a command that creates a new target bucket for logging. Notice the canned ACL argument that grants the system permission to write log files to this bucket.



Note

The source and the target buckets must be in the same location. For more information about bucket location constraints, see Buckets and Regions (p. 84)

```
$ ./s3curl.pl --id YOUR_AWS_ACCESS_KEY_ID --key YOUR_AWS_SECRET_ACCESS_KEY -
-acl log-delivery-write --put /dev/null -- -s -v http://s3.amazonaws.com/mylogs
```

2. If you just created a new bucket for logging, skip to the next section. Otherwise, to have your access logs files delivered to an existing bucket, you must modify the access control policy of that bucket by hand. Fetch the ?acl sub-resource of the target bucket and save it to a local file:

```
$ ./s3curl.pl --id YOUR_AWS_ACCESS_KEY_ID --key YOUR_AWS_SECRET_ACCESS_KEY -
--s -v 'http://s3.amazonaws.com/mylogs?acl' > mylogs.acl
```

3. Now open the local copy of the logging resource in your favorite text editor and insert a new <Grant> element to the <AccessControlList> section that gives the log delivery group WRITE and READ_ACP permission to your bucket.

```
<Grant>
```

Amazon Simple Storage Service Developer Guide Enabling Server Access Logging on the Source Bucket

4. Finally, apply the modified access control policy by writing it back to Amazon S3.

```
$ ./s3curl.pl --id <u>YOUR_AWS_ACCESS_KEY_ID</u> --key <u>YOUR_AWS_SECRET_ACCESS_KEY</u> --put mylogs.acl -- -s -v 'http://s3.amazonaws.com/mylogs?acl'
```

Enabling Server Access Logging on the Source Bucket

Now that the target bucket can accept log files, we'll update the <code>?logging</code> sub-resource of the source bucket to turn on server access logging. Remember that you must be the bucket owner to read or write this resource.

Fetch the ?logging sub-resource for modification using the command shown in the following example.

Example

```
$ ./s3curl.pl --id YOUR_AWS_ACCESS_KEY_ID --key YOUR_AWS_SECRET_ACCESS_KEY --
-s -v 'http://s3.amazonaws.com/mybucket?logging' > mybucket.logging
```

Amazon Simple Storage Service Developer Guide Enabling Server Access Logging on the Source Bucket

Open mybucket.logging in your favorite text editor and uncomment the <LoggingSettings> section. Replace the contents of the <TargetBucket> and <TargetPrefix> with 'mylogs' and 'mybucket-access log-' respectively.

Additionally, to grant users access to log files within the bucket, you can specify one or more users in the <TargetGrants> section, You can specify users through their e-mail address (EmailAddress) or canonical user ID (CanonicalUser). Permissions include READ, WRITE, and FULL_CONTROL. The result should be similar to the following.

Example

```
<?xml version="1.0" encoding="UTF-8"?>
<BucketLoggingStatus xmlns="http://doc.s3.amazonaws.com/2006-03-01">
    <LoggingEnabled>
        <TargetBucket>mylogs</TargetBucket>
        <TargetPrefix>mybucket-access_log-/</TargetPrefix>
            <TargetGrants>
         <Grant>
         <Grantee xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance"</pre>
xsi:type="AmazonCustomerByEmail">
             <EmailAddress>user@company.com</EmailAddress>
         </Grantee>
         <Permission>READ</permission>
     </Grant>
        </TargetGrants>
    </LoggingEnabled>
</BucketLoggingStatus>
```



Note

For general information about authentication, see Access Control (p. 204).

Now apply your modifications by writing the document back to the <code>?logging</code> sub-resource in Amazon S3.

Example

```
$ ./s3curl.pl --id YOUR_AWS_ACCESS_KEY_ID --key YOUR_AWS_SECRET_ACCESS_KEY -
-put mybucket.logging -- -s -v 'http://s3.amazonaws.com/mybucket?logging'
```

You can confirm your changes by fetching the <code>?logging</code> sub-resource and comparing it to what you just wrote.

Server access logging should now be enabled. Make a few requests against the source bucket now, and your access logs should begin to be delivered to the target bucket within the next few hours.

Disabling Server Logging for a Bucket

Fetch, modify, and apply the <code>?logging</code> sub resource in the same way as described in the preceding procedure, except use your text editor to remove the <code><LoggingEnabled></code> element.



Note

Log changes do not take effect immediately; logs will be delivered for a while after disabling logging.

Using the AWS SDKs and Explorers

Topics

- Using the AWS SDK for Java (p. 326)
- Using the AWS SDK for .NET (p. 327)
- Using the AWS SDK for PHP (p. 329)
- Using the AWS SDK for Ruby (p. 329)

You can use AWS SDKs when developing applications with Amazon S3. The AWS SDKs for Java, PHP, .NET, and Ruby wrap the underlying REST API, simplifying your programming tasks. Mobile SDKs are also available for building connected mobile applications using Amazon Web Services. This section provides an overview of using AWS SDKs for developing Amazon S3 applications. This section also describes how you can test the AWS SDK code samples provided in this guide.

In addition to the AWS SDKs, AWS Explorers are available for Visual Studio and Eclipse for Java IDE. In this case, the SDKs and the explorers are available bundled together as AWS Toolkits.

AWS Toolkit for Eclipse

The AWS Toolkit for Eclipse includes both the AWS SDK for Java and AWS Explorer for Eclipse. The AWS Explorer for Eclipse is an open source plug-in for Eclipse for Java IDE that makes it easier for developers to develop, debug, and deploy Java applications using Amazon Web Services. The easy to use GUI interface enables you to access and administer your AWS infrastructure including Amazon S3. You can perform common operations such as manage your buckets and objects, set IAM policies, while developing applications, all from within the context of Eclipse for Java IDE. For set up instructions, go to Setting Up the AWS Toolkit for Eclipse. For examples of using Amazon S3 using the explorer, go to Viewing and Editing Amazon S3 Buckets.

AWS Toolkit for Visual Studio

The AWS Explorer for Visual Studio is an extension for Microsoft Visual Studio that makes it easier for developers to develop, debug, and deploy .NET applications using Amazon Web Services. The easy to use GUI interface enables you to access and administer your AWS infrastructure including Amazon S3. You can perform common operations such as manage your buckets and objects, set IAM policies, while developing applications, all from within the context of Visual Studio. For set up instructions, go to Setting Up the AWS Toolkit for Visual Studio. For examples of using Amazon S3 using the explorer, go to Using Amazon S3 from AWS Explorer.

AWS SDKs

You can download only the SDKs. For information about downloading the SDK libraries, go to Sample Code Libraries.

Using the AWS SDK for Java

The AWS SDK for Java provides an API for the Amazon S3 bucket and object operations. For object operations, in addition to providing the API to upload objects in a single operation, the SDK provides API to upload large objects in parts (see Uploading Objects Using Multipart Upload API (p. 134)). The API gives you the option of using a high-level or low-level API.

Low-Level API

The Low-level APIs correspond to the underlying Amazon S3 REST operations, such as create, update, and delete operations that apply to buckets and objects. When you upload large objects using the low-level multipart upload API, it provides greater control such as letting you pause and resume multipart uploads, vary part sizes during the upload, or to begin uploads when you do not know the size of the data in advance. If you do not have these requirements, use the high-level API to upload objects.

High-Level API

For uploading objects, the SDK provides a higher level of abstraction by providing the TransferManager class. The high-level API is a simpler API, where in just a few lines of code you can upload files and streams to Amazon S3. You should use this API to upload data unless you need to control the upload as described in the preceding Low-Level API section.

For smaller data size the TransferManager API uploads data in a single operation. However, the TransferManager switches to using the multipart upload API when data size reaches certain threshold. When possible, the TransferManager uses multiple threads to concurrently upload the parts. If a part upload fails, the API retries the failed part upload up to three times. However, these are configurable options using the TransferManagerConfiguration class.



Note

When using a stream for the source of data, the TransferManager class will not do concurrent uploads.

The Java API Organization

The following packages in the AWS SDK for Java provide the API:

to configure the number of concurrent threads and the part size.

- **com.amazonaws.services.s3**—Provides the implementation APIs for Amazon S3 bucket and object operations.
 - For example, it provides methods to create buckets, upload objects, get objects, delete objects, and to list keys.
- com.amazonaws.services.s3.transfer—Provides the high-level API data upload.

 This high-level API is designed to further simplify uploading objects to Amazon S3. It includes the TransferManager class. It is particularly useful when uploading large objects in parts. It also includes the TransferManagerConfiguration class to configure advanced settings such as providing object metadata, specifying the storage class (STANDARD, REDUCED_REDUNDANCY) for storing objects, and setting object permissions using ACL. When uploading objects in parts, it provides options for you

 com.amazonaws.services.s3.model—Provides the low-level API classes to create requests and process responses.

For example, it includes the <code>GetObjectRequest</code> class to describe your get object request, the <code>ListObjectRequest</code> class to describe your list keys requests, and the <code>InitiateMultipartUploadRequest</code> and <code>InitiateMultipartUploadResult</code> classes when initiating a multipart upload.

For more information about the AWS SDK for Java API, go to AWS SDK for Java API Reference.

Testing the Java Code Examples

The easiest way to get started with the Java code examples is to install the latest AWS Toolkit for Eclipse. For information on installing or updating to the latest version, go to http://aws.amazon.com/eclipse. The following tasks guide you through the creation and testing of the Java code samples provided in this section.

General Process of Creating Java Code Examples

1	Create a new AWS Java project in Eclipse. The project is pre-configured with the AWS SDK for Java and it also includes the AwsCredentials.properties file for your AWS security credentials.
2	Copy the code from the section you are reading to your project.
3	Update the code by providing any required data. For example, if uploading a file, provide the file path and the bucket name.
4	Run the code. Verify that the object is created by using the AWS Management Console. For more information about the AWS Management Console, go to http://aws.amazon.com/console/ .

Using the AWS SDK for .NET

Topics

- The .NET API Organization (p. 328)
- Testing the .NET Code Examples (p. 328)

The AWS SDK for .NET provides the API for the Amazon S3 bucket and object operations. For object operations, in addition to providing the API to upload objects in a single operation, the SDK provides the API to upload large objects in parts (see Uploading Objects Using Multipart Upload API (p. 134)). The API gives you the option of using a high-level or low-level API.

Low-Level API

The Low-level APIs correspond to the underlying Amazon S3 REST operations, including the create, update, and delete operations that apply to buckets and objects. When you upload large objects using the low-level multipart upload API (see Uploading Objects Using Multipart Upload API (p. 134)) it provides greater control, such as letting you pause and resume multipart uploads, vary part sizes during the upload, or to begin uploads when you do not know the size of the data in advance. If you do not have these requirements, use the high-level API for uploading objects.

High-Level API

Amazon Simple Storage Service Developer Guide The .NET API Organization

For uploading objects, the SDK provides a higher level of abstraction by providing the TransferUtility class. The high-level API is a simpler API, where in just a few lines of code you can upload files and streams to Amazon S3. You should use this API to upload data unless you need to control the upload as described in the preceding Low-Level API section.

For smaller data size the TransferUtility API uploads data in a single operation. However, the TransferUtility switches to using the multipart upload API when data size reaches certain threshold. By default, it uses multiple threads to concurrently upload the parts. If a part upload fails, the API retries the failed part upload up to three times. However, these are configurable options.



Note

When using a stream for the source of data, the TransferUtility class will not do concurrent uploads.

The .NET API Organization

When writing Amazon S3 applications using the AWS SDK for .NET, you use the AWSSDK.dll. The following namespaces in this assembly provide the multipart upload API:

- Amazon.S3.Transfer—Provides the high-level API to upload your data in parts. It includes the TransferUtility class that enables you to specify a file, directory, or stream for uploading your data. It also includes the TransferUtilityUploadRequest and TransferUtilityUploadDirectoryRequest classes to configure advanced settings such as the number of concurrent threads, part size, object metadata, the storage class (STANDARD, REDUCED_REDUNDANCY) and object ACL.
- Amazon.S3—Provides the implementation for the low-level APIs.
 It provides methods that correspond to the Amazon S3 REST multipart upload API (see Using the REST API for Multipart Upload (p. 167)).
- Amazon.S3.Model—Provides the low-level API classes to create requests and process responses. For example, it provides the InitiateMultipartUploadRequest and InitiateMultipartUploadResponse classes you can use when initiating a multipart upload, and the UploadPartRequest and UploadPartResponse classes when uploading parts.

For more information about the AWS SDK for .NET API, go to AWS SDK for .NET Reference.

Testing the .NET Code Examples

The easiest way to get started with the .NET code examples is to install the AWS SDK for .NET. For more information, go to http://aws.amazon.com/sdkfornet. The following tasks guide you through creating and testing the C# code samples provided in this section.

General Process of Creating .NET Code Examples

Create a new Visual Studio project using the AWS Empty Project template.
In the AWS Access Credentials dialog box, provide your AWS credentials.
Note that the AWS Empty Project template is preconfigured with an App.config file for your AWS credentials and the following required references.
AWSSDK
System.Configuration
Verify your credentials in the App.config file.

4	Replace the code in the project file, Program.cs, with the code in the section you are reading.
5	Run the code. Verify that the object is created using the AWS Management Console. For more information about AWS Management Console, go to http://aws.amazon.com/console/.

Using the AWS SDK for PHP

The AWS SDK for PHP provides the API for Amazon S3 bucket and object operations. The API gives you the option of using a high-level or low-level API.

Low-Level API

The low-level APIs correspond to the underlying Amazon S3 REST operations, including the create, update, and delete operations on buckets and objects. The APIs provides greater control over these operations. For example, you can batch your requests and execute them in parallel, or when using the multipart upload API (see Uploading Objects Using Multipart Upload API (p. 134)), you can manage the object parts. Note that these low-level API calls return a response that includes all the Amazon S3 response details.

High-Level API

The high-level APIs are intended to simplify common use cases. For example, for uploading large objects using the low-level API, you must first initialize the multipart upload by calling the <code>initiate_multipart_upload()</code>, uploads parts by calling the <code>upload_part()</code> method and complete the upload by calling the <code>complete_multipart_upload()</code> methods. Instead, you could use the high-level API and upload object by calling the <code>create_mpu_object()</code> method. Internally, this API calls the low-level API to initialize the upload, upload object parts and complete the multipart upload. Another example is when enumerating objects in a bucket you can use the high-level API which returns all the keys, regardless of how many objects you have stored in the bucket. If you use the low-level API the response returns only up to 1,000 keys and if you have more than a 1,000 objects in the bucket, the result will be truncated and you will have to manage the response and check for any truncation.

Using the AWS SDK for Ruby

The AWS SDK for Ruby provides an API for Amazon S3 bucket and object operations. For object operations, you can use the API to upload objects in a single operation or upload large objects in parts (see Uploading Objects Using Multipart Upload). However, the API for a single operation upload can accept large objects as well and behind the scenes manage the upload in parts for you thereby reducing the amount of script you need to write.

The Ruby API Organization

When creating Amazon S3 applications using the AWS SDK for Ruby, you must install the AWS Ruby gem. For more information, see the AWS SDK for Ruby Getting Started Guide. Once installed, you can access the API, including the following key classes:

• AWS::S3—Represents the interface to Amazon S3 for the Ruby SDK.

The S3 class provides the #buckets instance method for accessing existing buckets or creating new ones.

AWS::S3::Bucket—Represents an Amazon S3 bucket.

Amazon Simple Storage Service Developer Guide Testing the Ruby Script Examples

The Bucket class provides the #objects instance method for accessing the objects in a bucket as well as methods to delete a bucket and return information about a bucket such as the bucket policy.

• AWS::S3::S3Object—Represents an Amazon S3 object identified by its key.

The S3Object class provides methods for getting and setting properties of an object, specifying the storage class for storing objects, and setting object permissions using access control lists. The S3Object class also has methods for deleting, uploading and copying objects. When uploading objects in parts, this class provides options for you to specify the order of parts uploaded and the part size.

For more information about the AWS SDK for Ruby API, go to AWS SDK for Ruby API Reference.

Testing the Ruby Script Examples

The easiest way to get started with the Ruby script examples is to install the latest AWS SDK for Ruby gem. For information about installing or updating to the latest gem, go to http://aws.amazon.com/sdkforruby/. The following tasks guide you through the creation and testing of the Ruby script examples assuming that you have installed the AWS SDK for Ruby.

General Process of Creating and Testing Ruby Script Examples

1	Create a new AWS Ruby script and add the following lines to the top of the script.	
	#!/usr/bin/env ruby	
	require 'rubygems' require 'aws-sdk'	
	The first line is the interpreter directive and the two require statements import two required gems into your script.	
2	Use the AWS::Core::Configuration class to specify your credentials.	
	<pre>AWS.config(:access_key_id => '*** Provide your access key ***, :secret_access_key => '*** Provide your secret key ***')</pre>	
3	Copy the code from the section you are reading to your script.	
4	Update the code by providing any required data. For example, if uploading a file, provide the file path and the bucket name.	
5	Run the script. Verify changes to buckets and objects by using the AWS Management Console. For more information about the AWS Management Console, go to http://aws.amazon.com/console/ .	

Appendices

This Amazon S3 developer guide appendix include the following sections.

Topics

- Appendix A: The Access Policy Language (p. 332)
- Appendix B: Using the SOAP API (p. 352)

Appendix A: The Access Policy Language

Topics

- Overview (p. 332)
- How to Write a Policy (p. 341)
- Special Information for Amazon S3 Policies (p. 352)

This appendix is for Amazon S3 users who want to write their own access control policies. You don't need to write your own policies if you want to allow access based only on AWS account ID and basic permissions. If you want to explicitly deny access or allow it based on finer conditions (like the time the request comes in or the IP address of the requester), you need to write your own policies and upload them to AWS.



Note

To write your own policies, you must be familiar with JSON. For more information, go to http://json.org.

The main portion of this appendix includes basic concepts you need to understand, how to write a policy, and the logic AWS uses to evaluate policies and decide whether to give the requester access to the resource. Although most of the information in this appendix is service-agnostic, there are some Amazon S3-specific details you need to know. For more information, see Special Information for Amazon S3 Policies (p. 352).

Overview

Topics

- Key Concepts (p. 332)
- Architectural Overview (p. 335)
- Using the Access Policy Language (p. 337)
- Evaluation Logic (p. 338)

This section describes basic concepts you need to understand to use access policy language to write policies. It also describes the general process for how access control works with the access policy language, and how policies are evaluated.

Key Concepts

The following sections describe the concepts you need to understand to use the access policy language. They're presented in a logical order, with the first terms you need to know at the top of the list.

Permission

A *permission* is the concept of allowing or disallowing some kind of access to a particular resource. Permissions essentially follow this form: "A is/isn't allowed to do B to C where D applies." For example, *Jane* (A) has permission to *put an object* (B) in *AcmeProductsBucket* (C) as long as an IP address is within a certain range (D). Whenever Jane sends a request to Amazon S3 to put an object in that bucket, the service checks to see if she has permission and if the request satisfies the conditions the bucket owner set forth in the policy.

Statement

A *statement* is the formal description of a single permission, written in the access policy language. You always write a statement as part of a broader container document known as a *policy* (see the next concept).

Policy

A *policy* is a document (written in JSON) that acts as a container for one or more statements. For example, a policy could have two statements in it: one that states that Jane can put objects in a specified bucket, and another that states that Bob cannot put objects into the same bucket. As shown in the following figure, an equivalent scenario would be to have two policies.



Amazon S3 uses the information in the statements (whether they're contained in a single policy or multiple) to determine if someone requesting access to a resource should be granted access.

Issuer

The *issuer* is the person who writes a policy to grant permissions for a resource. The issuer (by definition) is always the resource owner. AWS does not permit AWS service users to create policies for resources they don't own. If John is the resource owner, AWS authenticates John's identity when he submits the policy he's written to grant permissions for that resource.

Principal

The *principal* is the person or persons who receive the permission in the policy. The principal is A in the statement "A has permission to do B to C where D applies." In a policy, you can set the principal to "anyone" (i.e., you can specify a wildcard to represent all people). You might do this, for example, if you want to grant everyone (whether they are authenticated or anonymous) access to a subset of your Amazon S3 resources.

Action

The *action* is the activity the principal has permission to perform. The action is B in the statement "A has permission to do B to C where D applies." Typically, the action is just the operation in the request to AWS. You can specify one or multiple actions in a policy.

For the names of the Amazon S3 actions you can specify in a policy, see Amazon S3 Operations (p. 223).

Resource

The *resource* is the bucket or object the principal is requesting access to. The resource is C in the statement "A has permission to do B to C where D applies." You can specify one or more resources in a policy. For information about to specify a resource in a policy, see Specifying Amazon S3 Resources in Bucket Policies (p. 222).

Amazon Simple Storage Service Developer Guide Overview

Conditions and Keys

The *conditions* are any restrictions or details about the permission. The condition is D in the statement "A has permission to do B to C where D applies." The part of the policy that specifies the conditions can be the most detailed and complex of all the parts. Typical conditions are related to:

- Date and time (e.g., the request must arrive before a specific day)
- IP address (e.g., the requester's IP address must be part of a particular CIDR range)

A *key* is the specific characteristic that is the basis for access restriction. For example, the date and time of a request.

You use both *conditions* and *keys* together to express the restriction. The easiest way to understand how you actually implement a restriction is with an example: If you want to restrict access to before May 30, 2010, you use the condition called DateLessThan. You use the key called and set it to the value 2010-05-30T00:00:00Z. AWS defines the conditions and keys you can use. The might also define service-specific keys. For more information about conditions, see Condition (p. 345). For more information about the available keys, see Bucket Keys in Amazon S3 Policies (p. 224) and Object Keys in Amazon S3 Policies (p. 226).

Requester

The *requester* is the person who sends a request to an AWS service and asks for access to a particular resource. The requester sends a request to AWS that essentially says: "Will you allow me to do B to C where D applies?"

Evaluation

Evaluation is the process the AWS service uses to determine if an incoming request should be denied or allowed based on the applicable policies. For information about the evaluation logic, see Evaluation Logic (p. 338).

Effect

The *effect* is the result that you want a policy statement to return at evaluation time. You specify this value when you write the statements in a policy, and the possible values are *deny* and *allow*.

For example, you could write a policy that has a statement that *denies* all requests that come from Antarctica (effect=deny given that the request uses an IP address allocated to Antarctica). Alternately, you could write a policy that has a statement that *allows* all requests that *don't* come from Antarctica (effect=allow, given that the request doesn't come from Antarctica). Although the two statements sound like they do the same thing, in the access policy language logic, they are different. For more information, see Evaluation Logic (p. 338).

Although there are only two possible values you can specify for the effect (allow or deny), there can be three different results at policy evaluation time: *default deny*, *allow*, or *explicit deny*. For more information, see the following concepts and Evaluation Logic (p. 338).

Default Deny

A default deny is the default result from a policy in the absence of an allow or explicit deny.

Allow


An *allow* results from a statement that has effect=allow, assuming any stated conditions are met. Example: Allow requests if they are received before 1:00 p.m. on April 30, 2010. An allow overrides all default denies, but never an explicit deny.

Explicit Deny

An *explicit deny* results from a statement that has effect=deny, assuming any stated conditions are met. Example: Deny all requests if they are from Antarctica. Any request that comes from Antarctica will always be denied no matter what any other policies might allow.

Architectural Overview

The following figure and table describe the main components that interact to provide access control for your resources.



- You, the resource owner.
- Your resources (contained within the AWS service; e.g., Amazon S3 buckets or objects).
- Your policies.

 In Amazon S3 there is only one policy per bucket. Amazon S3 provides an API that enables to you to upload and manage your bucket policy. For information about the content of the policies, see How to Write a Policy (p. 341).
- Requesters and their incoming requests to the AWS service.

Amazon Simple Storage Service Developer Guide Overview




The access policy language evaluation code.

This is the set of code within the AWS service that evaluates incoming requests against the applicable policies and determines whether the requester is allowed access to the resource. For information about how the service makes the decision, see Evaluation Logic (p. 338).

For the typical process of how the components work together, see Using the Access Policy Language (p. 337).

Using the Access Policy Language

The following figure and table describe the general process of how access control works with the access policy language.



Process for Using Access Control with access policy language

You write a policy for your resource.
For example, you write a policy to specify permissions for your Amazon S3 objects. For more information, see How to Write a Policy (p. 341).
You upload your policy to AWS.
The AWS service itself provides an API you use to upload your policies. For example, you use the Amazon S3 PUT Bucket policy action to set a policy on a bucket.
Someone sends a request to use your resource.
For example, a user sends a request to Amazon S3 to upload an object to a bucket.
The AWS service determines which policies are applicable to the request.
For example, Amazon S3 looks at all the available Amazon S3 policies and determines which ones are applicable (based on what the resource is, who the requester is, etc.).
The AWS service evaluates the policies.
For example, Amazon S3 evaluates the policies and determines if the requester is allowed to upload the object to the bucket. For information about the decision logic, see Evaluation Logic (p. 338).
The AWS service either denies the request or continues to process it.
For example, based on the policy evaluation result, the service either returns an "Access denied" error to the requester or continues to process the request.

Related Topics


• Architectural Overview (p. 335)

Evaluation Logic

The goal at evaluation time is to decide whether a given request should be allowed or denied. The evaluation logic follows several basic rules:

- · By default, all requests to use your resource coming from anyone but you are denied
- · An allow overrides any default denies
- · An explicit deny overrides any allows
- The order in which the policies are evaluated is not important

The following flow chart and discussion describe in more detail how the decision is made.



Amazon Simple Storage Service Developer Guide Overview

The enforcement code then evaluates that are applicable to the request (based on the resource, principal, action, and conditions).

The order in which the enforcement code evaluates the policies is not important.

In all those policies, the enforcement code looks for an explicit deny instruction that would apply to the request.

If it finds even one, the enforcement code returns a decision of "deny" and the process is finished (this is an explicit deny; for more information, see Explicit Deny (p. 335)).

If no explicit deny is found, the enforcement code looks for any "allow" instructions that would apply to the request.

If it finds even one, the enforcement code returns a decision of "allow" and the process is done (the service continues to process the request).


If no allow is found, then the final decision is "deny" (because there was no explicit deny or allow, this is considered a default deny (for more information, see Default Deny (p. 334)).

The Interplay of Explicit and Default Denials

A policy results in a default deny if it doesn't directly apply to the request. For example, if an account requests to use Amazon S3, but the only policy that applies to the account states that the account can only list the contents of an Amazon S3 bucket, then that policy results in a default deny.

A policy also results in a default deny if a condition in a statement isn't met. If all conditions in the statement are met, then the policy results in either an allow or an explicit deny, based on the value of the *Effect* element in the policy.


For example, let's say you want to prevent requests coming in from Antarctica. You write a policy (called Policy A1) that allows a request only if it doesn't come from Antarctica. The following diagram illustrates the policy.



If someone sends a request from the U.S., the condition is met (the request is not from Antarctica). Therefore, the request is allowed. But, if someone sends a request from Antarctica, the condition isn't met, and the policy's result is therefore a default deny.


You could turn the result into an explicit deny by rewriting the policy (named Policy A2) as in the following diagram. Here, the policy explicitly denies a request if it comes from Antarctica.

Amazon Simple Storage Service Developer Guide Overview



If someone sends a request from Antarctica, the condition is met, and the policy's result is therefore an explicit deny.

The distinction between a default deny and an explicit deny is important because a default deny can be overridden by an allow, but an explicit deny can't. For example, let's say there's another policy that allows requests if they arrive on June 1, 2010. How does this policy affect the overall outcome when coupled with the policy restricting access from Antarctica? We'll compare the overall outcome when coupling the date-based policy (we'll call Policy B) with the preceding policies A1 and A2. Scenario 1 couples Policy A1 with Policy B, and Scenario 2 couples Policy A2 with Policy B. The following figure and discussion show the results when a request comes in from Antarctica on June 1, 2010.



In Scenario 1, Policy A1 returns a default deny, as described earlier in this section. Policy B returns an allow because the policy (by definition) allows requests that come in on June 1, 2010. The allow from Policy B overrides the default deny from Policy A1, and the request is therefore allowed.

In Scenario 2, Policy B2 returns an explicit deny, as described earlier in this section. Again, Policy B returns an allow. The explicit deny from Policy A2 overrides the allow from Policy B, and the request is therefore denied.

How to Write a Policy

Topics

- Basic Policy Structure (p. 342)
- Element Descriptions (p. 342)

• Supported Data Types (p. 350)


This section describes how to write policies and gives reference information about each policy element.

Basic Policy Structure

Each policy is a JSON document. As illustrated in the following figure, a policy includes:

- Optional policy-wide information (at the top of the document)
- · One or more individual statements

Each statement includes the core information about a single permission. If a policy includes multiple statements, we apply a logical OR across the statements at evaluation time. If multiple policies are applicable to a request, we apply a logical OR across the policies at evaluation time.



The information in a statement is contained within a series of *elements*. For information about these elements, see Element Descriptions (p. 342).

Element Descriptions

Topics

- Version (p. 343)
- Id (p. 343)
- Permission (p. 343)
- Statement (p. 343)
- Policy (p. 344)
- Issuer (p. 344)
- Sid (p. 344)

- Effect (p. 344)
- Principal (p. 344)
- Action (p. 344)
- NotAction (p. 345)
- Resource (p. 345)
- Condition (p. 345)

This section describes the elements you can use in a policy and its statements. The elements are listed here in the general order you use them in a policy. The Id, Version, and Statement are top-level policy elements; the rest are statement-level elements. JSON examples are provided.

All elements are optional for the purposes of parsing the policy document itself. The order of the elements doesn't matter (e.g., the Resource element can come before the Action element). You're not required to specify any Conditions in the policy.

Version

The Version is the access policy language version. This is an optional element, and currently the only allowed value is 2008-10-17.

```
"Version": "2008-10-17"
```

ld

The Id is an optional identifier for the policy. We recommend you use a UUID for the value, or incorporate a UUID as part of the ID to ensure uniqueness.



Important

Amazon S3, which implements the access policy language might require the *Id* element and have uniqueness requirements for it. For service-specific information about writing policies, see Special Information for Amazon S3 Policies (p. 352).

Permission

A permission is the concept of allowing or disallowing some kind of access to a particular resource. Permissions essentially follow this form: "A is/isn't allowed to do B to C where D applies." For example, Jane (A) has permission to receive messages (B) from John's Amazon SQS queue (C), as long as she asks to receive them before midnight on May 30, 2009 (D). Whenever Jane sends a request to Amazon SQS to use John's queue, the service checks to see if she has permission and if the request satisfies the conditions John set forth in the permission.

Statement

The Statement is the main element for a statement. It can include multiple elements (see the subsequent sections in this guide).

The Statement element contains an array of individual statements. Each individual statement is a distinct JSON block enclosed in curly brackets $\{ \}$.

```
"Statement":[{...},{...}]
```

Policy

A policy is a document (written in the access policy language) that acts as a container for one or more statements. For example, a policy could have two statements in it: one that states that Jane can read John's object, and another that states that Bob cannot read John's object. An equivalent scenario would be to have two policies, one containing the statement that Jane can read John's object, and another containing the statement that Bob cannot read John's object.

Issuer

The issuer is the person who writes a policy to grant permissions for a resource. The issuer (by definition) is always the resource owner. AWS does not permit AWS product users to create policies for resources they don't own. If John is the resource owner, AWS authenticates John's identity when he submits the policy he's written to grant permissions for that resource.

Sid

The Sid (statement ID) is an optional identifier you provide for the policy statement. Essentially it is just a sub-ID of the policy document's ID.



Important

The Amazon S3 implementation of the access policy language might require this element and have uniqueness requirements for it. For service-specific information about writing policies, see Special Information for Amazon S3 Policies (p. 352).

"Sid" : "1"

Effect

The Effect is a required element that indicates whether you want the statement to result in an allow or an explicit deny (for more information, see Explicit Deny (p. 335)).

Valid values for Effect are Allow and Deny.

"Effect": "Allow"

Principal

The Principal is the person or persons who receive or are denied permission according to the policy. You must specify the principal by using the principal's AWS account ID (e.g., 1234-5678-9012, with or without the hyphens). You can specify multiple principals, or a wildcard (*) to indicate all possible users. You can view your account ID by logging in to your AWS account at http://aws.amazon.com and clicking Account Activity.

In JSON, you use "AWS": as a prefix for the principal's AWS account ID.

Action

The Action is the specific type or types of access allowed or denied (for example, read or write). You can specify multiple values for this element. The values are free-form but must match values the AWS service expects (for more information, see Special Information for Amazon S3 Policies (p. 352)). You can use a wildcard (*) to give the principal access to all the actions the specific AWS service lets you share with other developers.

NotAction

The NotAction element is useful if you want to make an exception to a list of actions. You could use this, for example, if you want your users to be able to use only the GET Object.

The following example refers to all actions *other* than GET Object. You would use this in a policy with "Effect": "Deny" to keep users from accessing any other actions.

```
"NotAction": "s3:GetObject"
```

Resource


The Resource is the object or objects the policy covers. The value can include a multi-character match wildcard (*) or a single-character match wildcard (?) anywhere in the string. The values are free-form, but must follow the format the AWS service expects.

Condition


This section describes the Condition element and the information you can use inside the element.

The Condition Block


The Condition element is the most complex part of the policy statement. We refer to it as the *condition block*, because although it has a single Condition element, it can contain multiple conditions, and each condition can contain multiple key-value pairs. The following figure illustrates this. Unless otherwise specified for a particular key, all keys can have multiple values.




When creating a condition block, you specify the name of each condition, and at least one key-value pair for each condition. AWS defines the conditions and keys you can use (they're listed in the subsequent sections). An example of a condition is NumericEquals. Let's say you have a fictional resource, and you want to let John use it only if some particular numeric value *foo* equals either A or B, and another numeric value *bar* equals C. Then you would create a condition block that looks like the following figure.



Let's say you also want to restrict John's access to after January 1, 2009. Then you would add another condition, <code>DateGreaterThan</code>, with a date equal to January 1, 2009. The condition block would then look like the following figure.



As illustrated in the following figure, we always apply a logical AND to the conditions within a condition block, and to the keys within a condition. We always apply a logical OR to the values for a single key. All conditions must be met to return an allow or an explicit deny decision. If a condition isn't met, the result is a default deny.



As mentioned, AWS defines the conditions and keys you can use (for example, one of the keys is aws:CurrentTime, which lets you restrict access based on the date and time). The AWS service itself can also define its own service-specific keys. For a list of available keys, see Available Keys (p. 347).

For a concrete example that uses real keys, let's say you want to let John upload an object under the following three conditions:

- The time is after 12:00 noon on 8/16/2010
- The time is before 3:00 p.m. on 8/16/2010
- The request comes from an IP address within the 192.168.176.0/24 range or the 192.168.143.0/24 range

Your condition block has three separate conditions, and all three of them must be met for John to have access to your bucket .

The following shows what the condition block looks like in your policy.

```
"Condition" : {
    "DateGreaterThan" : {
        "aws:CurrentTime" : "2009-04-16T12:00:00Z"
    }
    "DateLessThan": {
        "aws:CurrentTime" : "2009-04-16T15:00:00Z"
    }
    "IpAddress" : {
        "aws:SourceIp" : ["192.168.176.0/24","192.168.143.0/24"]
    }
}
```

Available Keys

AWS provides a set of common keys supported by all AWS products that adopt the access policy language for access control. These keys are:

- aws:CurrentTime-For date/time conditions (see Date Conditions (p. 349))
- aws:SecureTransport—Boolean representing whether the request was sent using SSL (see Boolean Conditions (p. 349))
- aws:SourceIp-The requester's IP address, for use with IP address conditions (see IP Address (p. 349))
- aws:UserAgent-Information about the requester's client application, for use with string conditions (see String Conditions (p. 348))
- aws:EpochTime-Number of seconds since epoch.
- aws:Referer-Same as the HTTP referer field.

The key names are case insensitive. For example, aws:CurrentTime is equivalent to AWS:currenttime.



Note

If you use aws: SourceIp, and the request comes from an Amazon EC2 instance, we evaluate the instance's public IP address to determine if access is allowed.

Each AWS service that uses the access policy language might also provide service-specific keys. For a list of any service-specific keys you can use, see Special Information for Amazon S3 Policies (p. 352).

Condition Types

These are the general types of conditions you can specify:

String

- Numeric
- · Date and time
- Boolean
- IP address
- Amazon Resource Name (ARN)

String Conditions

String conditions let you constrain using string matching rules. The actual data type you use is a string.

Condition	Description
StringEquals	Strict matching Short version: streq
StringNotEquals	Strict negated matching Short version: strneq
StringEqualsIgnoreCase	Strict matching, ignoring case Short version: streqi
StringNotEqualsIgnoreCase	Strict negated matching, ignoring case Short version: strneqi
StringLike	Loose case-insensitive matching. The values can include a multi-character match wildcard (*) or a single-character match wildcard (?) anywhere in the string. Short version: strl
StringNotLike	Negated loose case-insensitive matching. The values can include a multi-character match wildcard (*) or a single-character match wildcard (?) anywhere in the string. Short version: strnl

Numeric Conditions

Numeric conditions let you constrain using numeric matching rules. You can use both whole integers or decimal numbers. Fractional or irrational syntax is not supported.

Condition	Description
NumericEquals	Strict matching Short version: numeq
NumericNotEquals	Strict negated matching Short version: numneq
NumericLessThan	"Less than" matching Short version: numlt
NumericLessThanEquals	"Less than or equals" matching Short version: numlteq

Condition	Description
NumericGreaterThan	"Greater than" matching Short version: numgt
NumericGreaterThanEquals	"Greater than or equals" matching Short version: numgteq

Date Conditions

Date conditions let you constrain using date and time matching rules. You must specify all date/time values with one of the W3C implementations of the ISO 8601 date formats (for more information, go to http://www.w3.org/TR/NOTE-datetime). You use these conditions with the aws:CurrentTime key to restrict access based on request time.



Note

Wildcards are not permitted for date conditions.

Condition	Description
DateEquals	Strict matching Short version: dateeq
DateNotEquals	Strict negated matching Short version: dateneq
DateLessThan	A point in time at which a key stops taking effect Short version: datelt
DateLessThanEquals	A point in time at which a key stops taking effect Short version: datelteq
DateGreaterThan	A point in time at which a key starts taking effect Short version: dategt
DateGreaterThanEquals	A point in time at which a key starts taking effect Short version: dategteq

Boolean Conditions

Condition	Description
Bool	Strict Boolean matching

IP Address

IP address conditions let you constrain based on IP address matching rules. You use these with the aws:SourceIp key. The value must be in the standard CIDR format (for example, 10.52.176.0/24). For more information, go to RFC 4632.

Condition	Description	
IpAddress	Whitelisting based on the IP address or range	
NotIpAddress	Blacklisting based on the IP address or range	

Amazon Resource Name (ARN)

Amazon Resource Name (ARN) conditions let you constrain based on ARN matching rules. The actual data type you use is a string.

Condition	Description
ArnEquals	Strict matching for ARN Short version: arneq
ArnNotEquals	Strict negated matching for ARN Short version: arnneq
ArnLike	Loose case-insensitive matching of the ARN. Each of the six colon-delimited components of the ARN is checked separately and each can include a multi-character match wildcard (*) or a single-character match wildcard (?). Short version: arn1
ArnNotLike	Negated loose case-insensitive matching of the ARN. The values can include a multi-character match wildcard (*) or a single-character match wildcard (?) anywhere in the string. Short version: arnnl

Supported Data Types

This section lists the set of data types the access policy language supports. The language doesn't support all types for each policy element (for the supported data types for each element, see Element Descriptions (p. 342)).

The access policy language supports the following data types:

- Strings
- Numbers (Ints and Floats)
- Boolean
- Null
- Lists
- Maps
- Structs (which are just nested Maps)

The following table maps each data type to the serialization. Note that all policies must be in UTF-8. For information about the JSON data types, go to RFC 4627.

Туре	JSON
String	String
Integer	Number
Float	Number
Boolean	true false
Null	null
Date	String adhering to the W3C Profile of ISO 8601
IpAddress	String adhering to RFC 4632
List	Array
Object	Object

Special Information for Amazon S3 Policies

The following list describes the restrictions on Amazon S3 policies:

- The maximum size of a policy is 20 KB
- The value for Resource must be prefixed with the bucket name or the bucket name and a path under it (bucket/*). If only the bucket name is specified, without the trailing /*, the policy applies to the bucket.
- Each policy must have a unique policy ID (Id)
- Each statement in a policy must have a unique statement ID (sid)
- Each policy must cover only a single bucket and resources within that bucket (when writing a policy, don't include statements that refer to other buckets or resources in other buckets)

Appendix B: Using the SOAP API

This section contains information specific to the Amazon S3 SOAP API.



Note

SOAP requests, both authenticated and anonymous, must be sent to Amazon S3 using SSL. Amazon S3 returns an error when you send a SOAP request over HTTP.

Common SOAP API Elements

You can interact with Amazon S3 using SOAP 1.1 over HTTP. The Amazon S3 WSDL, which describes the Amazon S3 API in a machine-readable way, is available at:

http://doc.s3.amazonaws.com/2006-03-01/AmazonS3.wsdl. The Amazon S3 schema is available at http://doc.s3.amazonaws.com/2006-03-01/AmazonS3.xsd.

Most users will interact with Amazon S3 using a SOAP toolkit tailored for their language and development environment. Different toolkits will expose the Amazon S3 API in different ways. Please refer to your specific toolkit documentation to understand how to use it. This section illustrates the Amazon S3 SOAP operations in a toolkit-independent way by exhibiting the XML requests and responses as they appear "on the wire."

Common Elements

You can include the following authorization-related elements with any SOAP request:

- AWSAccessKeyId: The AWS Access Key ID of the requester
- Timestamp: The current time on your system
- Signature: The signature for the request

For information about endpoints, see Request Endpoints (p. 12).

Authenticating SOAP Requests

Every non-anonymous request must contain authentication information to establish the identity of the principal making the request. In SOAP, the authentication information is put into the following elements of the SOAP request:

AWSAccessKeyId: Your AWS Access Key ID

Amazon Simple Storage Service Developer Guide Setting Access Policy with SOAP

- Timestamp: This must be a dateTime (go to http://www.w3.org/TR/xmlschema-2/#dateTime) in the Coordinated Universal Time (Greenwich Mean Time) time zone, such as 2009-01-01T12:00:00.000Z. Authorization will fail if this timestamp is more than 15 minutes away from the clock on Amazon S3 servers.
- Signature: The RFC 2104 HMAC-SHA1 digest (go to http://www.ietf.org/rfc/rfc2104.txt) of the
 concatenation of "AmazonS3" + OPERATION + Timestamp, using your AWS Secret Access Key as
 the key. For example, in the following CreateBucket sample request, the signature element would
 contain the HMAC-SHA1 digest of the value "AmazonS3CreateBucket2009-01-01T12:00:00.000Z":

For example, in the following CreateBucket sample request, the signature element would contain the HMAC-SHA1 digest of the value "AmazonS3CreateBucket2009-01-01T12:00:00.000Z":

Example



Note

SOAP requests, both authenticated and anonymous, must be sent to Amazon S3 using SSL. Amazon S3 returns an error when you send a SOAP request over HTTP.



Important

Due to different interpretations regarding how extra time precision should be dropped, .NET users should take care not to send Amazon S3 overly specific time stamps. This can be accomplished by manually constructing <code>DateTime</code> objects with only millisecond precision.

For more information, see the sample .NET SOAP libraries for an example of how to do this.

Setting Access Policy with SOAP

Access control can be set at the time a bucket or object is written by including the "AccessControlList" element with the request to CreateBucket, PutObjectInline, or PutObject. The AccessControlList element is described in Access Control (p. 204). If no access control list is specified with these operations, the resource is created with a default access policy that gives the requester FULL_CONTROL access (this is the case even if the request is a PutObjectInline or PutObject request for an object that already exists).

Following is a request that writes data to an object, makes the object readable by anonymous principals, and gives the specified user FULL_CONTROL rights to the bucket (Most developers will want to give themselves FULL_CONTROL access to their own bucket).

Amazon Simple Storage Service Developer Guide Setting Access Policy with SOAP

Example

Following is a request that writes data to an object and makes the object readable by anonymous principals.

Sample Request

```
<PutObjectInline xmlns="http://doc.s3.amazonaws.com/2006-03-01">
  <Bucket>quotes</Bucket>
  <Key>Nelson</Key>
  <Metadata>
    <Name>Content-Type</Name>
   <Value>text/plain</Value>
  </Metadata>
  <Data>aGEtaGE=</Data>
  <ContentLength>5</ContentLength>
  <AccessControlList>
    <Grant>
      <Grantee xsi:type="CanonicalUser">
      <ID>a9a7b886d6fd24a52fe8ca5bef65f89a64e0193f23000e241bf9b1c61be666e9</ID>
        <DisplayName>chriscustomer</DisplayName>
      </Grantee>
      <Permission>FULL_CONTROL</Permission>
    </Grant>
    <Grant>
      <Grantee xsi:type="Group">
        <URI>http://acs.amazonaws.com/groups/global/AllUsers<URI>
      </Grantee>
      <Permission>READ</Permission>
    </Grant>
  </AccessControlList>
  <AWSAccessKeyId>1D9FVRAYCP1VJEXAMPLE=</AWSAccessKeyId>
  <Timestamp>2009-03-01T12:00:00.183Z</Timestamp>
  <Signature>Iuyz3d3P0aTou39dzbgaEXAMPLE=</signature>
</PutObjectInline>
```

Sample Response

The access control policy can be read or set for an existing bucket or object using the GetBucketAccessControlPolicy, GetObjectAccessControlPolicy, SetBucketAccessControlPolicy, and SetObjectAccessControlPolicy methods. For more information, see the detailed explanation of these methods.

Amazon S3 Resources

Following is a table that lists related resources that you'll find useful as you work with this service.

Resource	Description
Amazon S3 Getting Started Guide	The Getting Started Guide provides a quick tutorial of the service based on a simple use case.
Amazon S3 API Reference	The API Reference describes Amazon S3 operations in detail.
Amazon S3Technical FAQ	The FAQ covers the top 20 questions developers have asked about this product.
Amazon S3 Release Notes	The Release Notes give a high-level overview of the current release. They specifically note any new features, corrections, and known issues.
AWS Developer Resource Center	A central starting point to find documentation, code samples, release notes, and other information to help you build innovative applications with AWS.
AWS Management Console	The console allows you to perform most of the functions of Amazon S3without programming.
Discussion Forums	A community-based forum for developers to discuss technical questions related to Amazon Web Services.
AWS Support Center	The home page for AWS Technical Support, including access to our Developer Forums, Technical FAQs, Service Status page, and Premium Support.
AWS Calculator	Use the AWS calculator to estimate your monthly charges for using AWS services.
AWS Premium Support	The primary web page for information about AWS Premium Support, a one-on-one, fast-response support channel to help you build and run applications on AWS Infrastructure Services.
Amazon S3 product information	The primary web page for information about Amazon S3.

Resource	Description
Contact Us	A central contact point for inquiries concerning AWS billing, account, events, abuse etc.
Conditions of Use	Detailed information about the copyright and trademark usage at Amazon.com and other topics.

Document History

This document history is associated with the 2006-03-01 release of Amazon S3. This guide was last updated on 17 October 2011.

The following table describes the important changes since the last release of the *Amazon S3 Developer Guide*.

Change	Description	Date
Documentation Update	In addition to documentation bug fixes, this release includes the following enhancements: • New server-side enryption sections using the AWS SDK for PHP (see Specifying Server-Side Encryption Using the AWS)	In this release.
	SDK for PHP (p. 251)) and the AWS SDK for Ruby (see Specifying Server-Side Encryption Using the AWS SDK for Ruby (p. 253)).	
	New section on creating and testing Ruby samples (see Using the AWS SDK for Ruby (p. 329)).	
Server-side encryption support	Amazon S3 now supports server-side encryption. It enables you to request Amazon S3 to encrypt your data at rest, that is, encrypt your object data when Amazon S3 writes your data to disks in its data centers. In addition to REST API updates, the AWS SDK for Java and .NET provide necessary functionality to request server-side encryption. You can also request server-side encryption when uploading objects using AWS Management Console. To learn more about data encryption, go to Using Data Encryption.	04 October 2011

Change	Description	Date
Documentation Update	 In addition to documentation bug fixes, this release includes the following enhancements: Added Ruby and PHP samples to the Making Requests (p. 10) section. Added sections describing how to generate and use pre-signed URLs. For more information, see Share an Object with Others (p. 118) and Uploading Objects Using Pre-Signed URLs (p. 168). Updated an existing section to introduce AWS Explorers for Eclipse and Visual Studio. For more information, see Using the AWS SDKs and Explorers (p. 325). 	22 September 2011
Support for sending requests using temporary security credentials	In addition to using your AWS account and IAM user security credentials to send authenticated requests to Amazon S3, you can now send requests using temporary security credentials you obtain from AWS Identity and Access Management (IAM). You can use the AWS Security Token Service API or the AWS SDK wrapper libraries to request these temporary credentials from IAM. You can request these temporary security credentials for your own use or hand them out to federated users and applications. This feature enables you to manage your users outside AWS and provide them with temporary security credentials to access your AWS resources. For more information, see Making Requests (p. 10). For more information about IAM support for temporary security credentials, go to Granting Temporary Access to Your AWS Resources.	3 August 2011
Multipart Upload API extended to enable copying objects up to 5 TB	Prior to this release, Amazon S3 API supported copying objects of up to 5 GB in size. To enable copying objects larger than 5 GB, Amazon S3 now extends the multipart upload API with a new operation, Upload Part (Copy). You can use this multipart upload operation to copy objects up to 5 TB in size. For more information, see Copying Objects (p. 175). For conceptual information about multipart upload API, see Uploading Objects Using Multipart Upload API (p. 134).	21 June 2011
SOAP API calls over HTTP disabled	To increase security, SOAP API calls over HTTP are disabled. Authenticated and anonymous SOAP requests must be sent to Amazon S3 using SSL.	6 June 2011

Change	Description	Date
IAM enables cross-account delegation	Previously, to access an Amazon S3 resource, an IAM user needed permissions from both the parent AWS account and the Amazon S3 resource owner. With cross-account access, the IAM user now only needs permission from the owner account. That is, If a resource owner grants access to an AWS account, the AWS account can now grant its IAM users access to these resources. For more information, go to Enabling Cross-Account Access in Using Identity and Access Management. For more information on specifying principals in a bucket policy, see Specifying Principals in Bucket Policies (p. 223).	6 June 2011
New link	This service's endpoint information is now located in the Amazon Web Services General Reference. For more information, go to Regions and Endpoints in Amazon Web Services General Reference.	1 March 2011
Support for hosting static websites in Amazon S3	Amazon S3 introduces enhanced support for hosting static websites. This includes support for index documents and custom error documents. When using these features, requests to the root of your bucket or a subfolder (e.g., http://mywebsite.com/subfolder) returns your index document instead of the list of objects in your bucket. If an error is encountered, Amazon S3 returns your custom error message instead of an Amazon S3 error message. For more information, see Hosting Websites on Amazon S3 (p. 283).	17 February 2011
Response Header API Support	The GET Object REST API now allows you to change the response headers of the REST GET Object request for each request. That is, you can alter object metadata in the response, without altering the object itself. For more information, see Getting Objects (p. 109).	14 January 2011
Large object support	Amazon S3 has increased the maximum size of an object you can store in an S3 bucket from 5 GB to 5 TB. If you are using the REST API you can upload objects of up to 5 GB size in a single PUT operation. For larger objects, you must use the Multipart Upload REST API to upload objects in parts. For more information, see Uploading Objects Using Multipart Upload API (p. 134).	9 December 2010
Multipart upload	Multipart upload enables faster, more flexible uploads into Amazon S3. It allows you to upload a single object as a set of parts. For more information, see Uploading Objects Using Multipart Upload API (p. 134).	10 November 2010
Canonical ID support in bucket policies	You can now specify canonical IDs in bucket policies. For more information, see Specifying Principals in Bucket Policies (p. 223) and for a sample, see Granting Permission, Using Canonical ID, to a CloudFront Origin Identify (p. 222)	17 September 2010
Amazon S3 works with IAM	This service now integrates with AWS Identity and Access Management (IAM). For more information, go to Integrating with Other AWS Products in Using AWS Identity and Access Management.	2 September 2010

Change	Description	Date
Notifications	The Amazon S3 notifications feature enables you to configure a bucket so that Amazon S3 publishes a message to an Amazon Simple Notification Service (SNS) topic when Amazon S3 detects a key event on a bucket. For more information, see Setting Up Notification of Bucket Events (p. 292).	14 July 2010
Bucket policies	Bucket policies is an access management system you use to set access permissions across buckets, objects, and sets of objects. This functionality supplements and in many cases replaces access control lists. For more information, see Bucket Policies (p. 7).	6 July 2010
Path-style syntax available in all regions	Amazon S3 now supports the path-style syntax for any bucket in the US Classic Region, or if the bucket is in the same region as the endpoint of the request. For more information, see Virtual Hosting (p. 59).	9 June 2010
New endpoint for EU (Ireland)	Amazon S3 now provides an endpoint for EU (Ireland): http://s3-eu-west-1.amazonaws.com.	9 June 2010
Console	You can now use Amazon S3 through the AWS Management Console. You can read about all of the Amazon S3 functionality in the console in the <i>Amazon S3 Console User Guide</i> .	9 June 2010
Reduced Redundancy	Amazon S3 now enables you to reduce your storage costs by storing objects in Amazon S3 with reduced redundancy. For more information, see Reduced Redundancy Storage (p. 6).	12 May 2010
New Region supported	Amazon S3 now supports the Asia Pacific (Singapore) Region. For more information, see Buckets and Regions (p. 84).	28 April 2010
Object Versioning	This release introduces object versioning. All objects now can have a key and a version. If you enable versioning for a bucket, Amazon S3 gives all objects added to a bucket a unique version ID. This feature enables you to recover from unintended overwrites and deletions. For more information, see Versioning (p. 8) and Using Versioning (p. 262).	8 February 2010
New Region supported	Amazon S3 now supports the US-West (Northern California) Region. The new endpoint for requests to this Region is s3-us-west-1.amazonaws.com. For more information, see Buckets and Regions (p. 84).	2 December 2009
AWS SDK for .NET	AWS now provides libraries, sample code, tutorials, and other resources for software developers who prefer to build applications using .NET language-specific APIs instead of REST or SOAP. These libraries provide basic functions (not included in the REST or SOAP APIs), such as request authentication, request retries, and error handling so that it's easier to get started. For more information about language-specific libraries and resources, see AWS Library Support, or go to Working With Amazon S3 in the Amazon Simple Storage Service Getting Started Guide.	11 November 2009

Glossary

100-continue A method that enables a client to see if a server can accept a request before

actually sending it. For large ${ t PUTs}$, this can save both time and bandwidth charges.

account AWS account associated with a particular developer.

authentication The process of proving your identity to the system.

bucket A container for objects stored in Amazon S3. Every object is contained within a

bucket. For example, if the object named photos/puppy.jpg is stored in the

johnsmith bucket, then it is addressable using the URL

http://johnsmith.s3.amazonaws.com/photos/puppy.jpg

canned access policy A standard access control policy that you can apply to a bucket or object. Options

include: private, public-read, public-read-write, authenticated-read.

canonicalization The process of converting data into a standard format that will be recognized by

a service such as Amazon S3.

consistency model The method through which Amazon S3 achieves high availability, which involves

replicating data across multiple servers within Amazon's data centers. After a "success" is returned, your data is safely stored. However, information about the

changes might not immediately replicate across Amazon S3.

delete marker A Delete Marker is an object with a key and version ID but it has no content.

Amazon S3 inserts Delete Markers automatically into buckets when a DELETE request is executed on an object in a bucket where Versioning is enabled.

default deny A permission that defaults to DENY.

key The unique identifier for an object within a bucket. Every object in a bucket has

exactly one key. Since a bucket and key together uniquely identify each object, Amazon S3 can be thought of as a basic data map between "bucket + key" and the object itself. Every object in Amazon S3 can be uniquely addressed through the combination of the web service endpoint, bucket name, and key, as in http://doc.s3.amazonaws.com/2006-03-01/AmazonS3.wsdl, where "doc" is the

name of the bucket, and "2006-03-01/AmazonS3.wsdl" is the key.

metadata The metadata is a set of name-value pairs that describe the object. These include

default metadata such as the date last modified and standard HTTP metadata such as Content-Type. The developer can also specify custom metadata at the

time the Object is stored.

Amazon Simple Storage Service Developer Guide

null object A null object is one whose version ID is null. Amazon S3 adds a null object to

a bucket when version for that bucket is suspended. It is possible to have only

one null object for each key in a bucket.

object The fundamental entities stored in Amazon S3. Objects consist of object data

and metadata. The data portion is opaque to Amazon S3.

part A contiguous portion of object's data. The Amazon S3 multipart upload feature

allows larger objects to be uploaded in parts. These object parts can be uploaded independently and in any order. If transmission of any part fails, that part can be retransmitted without affecting other parts. After all the object parts are uploaded,

Amazon S3 assembles these parts and creates the object.

service endpoint The host and port with which you are trying to communicate within the destination

URL. For virtual hosted-style requests, this is mybucket.s3.amazonaws.com.

For path-style requests, this is s3.amazonaws.com

Versioning Every object in Amazon S3 has a key and a version ID. Objects with the same

key but different version IDs can be stored in the same bucket. Versioning is

enabled at the bucket layer using PUT Bucket versioning.

SOAP API, 8 Index configuring bucket, 290 configuring logging, 313 consistency model, 4 **Symbols** costs, 9 100-continue, 64 D data model, 4 delete multipart upload, 106 access control, 204 delimiter, 194 access control policies, 332 DevPay, 304 access logs, 315 DNS, 299 access policy DNS routing, 296, 297, 298 **SOAP, 353** Adobe Flash, 65 Е Amazon DevPay, 304 API, 8 elements REST, 8, 45 REST, 233, 237, 237, 243, 326, 327, 329, 329 SOAP, 8 SOAP, 352 appendix, 331 errors, 309 authentication, 204 details, 309 debugging, 57 isolation, 310 REST, 48 messages, 309 SOAP, 352 response, 309 authentication header, 49 REST response, 308 SlowDown, 310 B SOAP response, 309 events billing, 9 setting up notification of, 292 BitTorrent, 301 charges, 301 F publishing, 303 retrieving objects, 302 features, 2 browser uploads, 65 file size, maximum, 2 bucket permissions, 290 Flash, Adobe, 65 buckets, 3, 82 access control, 99 G billing, 99 glossary, resources, mime configuration, 84 creating a job, 331 location selection, 84 guide organization, 1 notifications of events, 292 restrictions, 83 Н virtual hosting, 59 hosting websites, 283, 284, 285 C manage website configuration, 86 HTTP user agents, 63 CanonicalizedAmzHeaders element, 51 changes, 357 charges, 9 client-side encryption, 254 index document, 283 components, 3 initiate multipart upload, 106 concepts introduction, 2 API, 8 buckets, 3 J components, 3 Java, 299 keys, 3 iava sdk objects, 3 multipart upload, 135 operations, 8 JVM cache, 299 REST API, 8

K	R
keys, 3	redirection, 63
listing hierarchically, 194	permanent, 298
multi-page results, 194	request, 296
using, 193	temporary, 297
	Reduced Redundancy Storage, 260
L	referrer, 316
list multipart upload parts, 106	Region, 84, 352
listing keys, hierarchically, 194	request redirection, 296
location constraints, 84	access policy, 63 request routing, 296
logs, 312	REST
best effort delivery, 316	API, 45
changing settings, 315	authentication, 48
configuration, 313	examples, 52
delivery, 315	header, 49
format, 316	debugging authentication, 57
setting up, 320	elements, 233, 237, 237, 243, 326, 327, 329, 329
NA.	POST, 65
M	StringToSign, 52
manage s3 website AWS SDK, 87, 90, 94	time stamp, 52
manage s3 website configuration, 86	restrictions, 83
manage s3 website using REST, 95	routing, 296
manage website configuration using console, 86	DNS, 296
metadata, using, 101	RRS, 260
model, 4	0
multipart upload java sdk, 135	S
large object upload, 134	s3 bucket as website, 283, 290
large objects, 134	S3 bucket as website, 284
REST API, 167, 185	S3 endpoints, 285
multipart upload process, 106	s3 website hosting, 290
multipart upload using aws sdk, 145, 161	s3 website index document, 287
	server access logs, 312, 315
N	server-side encryption, 247 SetObjectAccessControlPolicy
notifications	SOAP, 301
setting up, 292	shared queues, 332
3 1, 1	signature, creating, 57
0	size, object, 2
object size, maximum, 2	SOAP
objects, 3	access policy, 353
getting, 110	authentication, 352
using, 100	elements, 352
operations, 8	error response, 309
organization of guide, 1	storage limit, 2
overview, 2	StringToSign, 52
	system metadata, 101
P	Т
pagination, 194	
paying, 9	TCP optimization, 300
performance optimization, 300	time stamp, 52
PHP virtual machine, 299	TTLs, clients, 299
policies, 332	U
POST, 65	_
prefix, 194	uploads, browser, 65
	user metadata, 101



versioning, 262 virtual hosted buckets, 59 virtual machines, 299



website configuration, 290