Continuuity Reactor 2.3.0

Installation and Configuration Guide

Contents

| Introduction | 3 |
|--|----|
| Conventions | 3 |
| System Requirements | 4 |
| Hardware Requirements | 4 |
| Network Requirements | 4 |
| Software Prerequisites | 5 |
| Java Runtime | 5 |
| Node.js Runtime | 5 |
| Hadoop/HBase Environment | 5 |
| Prepare the Cluster | 6 |
| Secure Hadoop | 7 |
| ULIMIT Configuration | 7 |
| Packaging | 8 |
| RPM using Yum | 8 |
| Debian using APT | 9 |
| Installation | 10 |
| Upgrading From a Previous Version | 11 |
| Verification | 12 |
| Troubleshooting | 13 |
| Application Won't Start | 13 |
| No Metrics/logs | 13 |
| Only the First Flowlet Showing Activity | 13 |
| YARN Application Shows ACCEPTED For Some Time But Then Fails | 13 |
| Log Saver Process Throws an Out-of-Memory Error, Reactor Dashboard Shows Service Not OK | 13 |
| Annendix: continuuity-site xml | 15 |

Introduction

This guide is to help you install and configure Continuuity Reactor. It provides the system, network, and software requirements, packaging options, and instructions for installation and verification of the Continuuity Reactor components so they work with your existing Hadoop cluster.

These are the Continuuity Reactor components:

- Continuuity Web-App: User interface—the Dashboard—for managing Continuuity Reactor applications;
- Continuuity Gateway: Service supporting REST endpoints for Continuuity Reactor;
- **Continuuity Reactor-Master**: Service for managing runtime, lifecycle and resources of Reactor applications;
- Continuuity Kafka: Metrics and logging transport service, using an embedded version of Kafka; and
- Continuuity Authentication Server: Performs client authentication for Reactor when security is enabled.

Before installing the Continuouity Reactor components, you must first install a Hadoop cluster with HDFS, YARN, HBase, and Zookeeper. In order to use the ad-hoc querying capabilities of Reactor, you will also need Hive. All Reactor components can be installed on the same boxes as your Hadoop cluster, or on separate boxes that can connect to the Hadoop services.

Our recommended installation is to use two boxes for the Reactor components; the hardware requirements are relatively modest, as most of the work is done by the Hadoop cluster. These two boxes provide high availability; at any one time, one of them is the leader providing services while the other is a follower providing failover support.

Some Reactor components run on YARN, while others orchestrate the Hadoop cluster. The Continuuity Gateway service starts a router instance on each of the local boxes and instantiates one or more gateway instances on YARN as determined by the gateway service configuration.

We have specific hardware, network and prerequisite software requirements detailed below that need to be met and completed before installation of the Continuuity Reactor components.

For information on configuring the Reactor for security, see the online document Reactor Security Guide.

Conventions

In this document, *client* refers to an external application that is calling the Continuuity Reactor using the HTTP interface.

Application refers to a user Application that has been deployed into the Continuuity Reactor.

Text that are variables that you are to replace is indicated by a series of angle brackets (< >). For example:

https://<username>:<password>@repository.continuuity.com

indicates that the texts <username> and <password> are variables and that you are to replace them with your values, perhaps username john_doe and password BigData11:

https://john_doe:BigDatall@repository.continuuity.com

System Requirements

Hardware Requirements

Systems hosting the Continuuity Reactor components must meet these hardware specifications, in addition to having CPUs with a minimum speed of 2 GHz:

| Continuuity Component | Hardware Component | Specifications |
|-----------------------------------|-----------------------|--|
| Continuuity Web-App | RAM | 1 GB minimum, 2 GB recommended |
| Continuuity Gateway | RAM | 2 GB minimum, 4 GB recommended |
| Continuuity Reactor-Master | RAM | 2 GB minimum, 4 GB recommended |
| Continuuity Kafka | RAM | 1 GB minimum, 2 GB recommended |
| | Disk Space | Continuuity Kafka maintains a data cache in a configurable data directory. Required space depends on the number of Continuuity applications deployed and running in the Continuuity Reactor and the quantity of logs and metrics that they generate. |
| Continuuity Authentication Server | RAM | 1 GB minimum, 2 GB recommended |

Network Requirements

Continuuity components communicate over your network with *HBase*, *HDFS*, and *YARN*. For the best performance, Continuuity components should be located on the same LAN, ideally running at 1 Gbps or faster. A good rule of thumb is to treat Continuuity components as you would *Hadoop DataNodes*.

Software Prerequisites

You'll need this software installed:

- Java runtime (on Reactor and Hadoop nodes)
- Node.js runtime (on Reactor nodes)
- Hadoop, HBase (and possibly Hive) environment to run against

Java Runtime

The latest JDK or JRE version 1.6.xx for Linux and Solaris must be installed in your environment.

Once you have installed the JDK, you'll need to set the JAVA_HOME environment variable.

Node.js Runtime

You can download the latest version of Node.js from nodejs.org:

- 1. Download the appropriate Linux or Solaris binary .tar.gz from nodejs.org/download/.
- 2. Extract somewhere such as /opt/node-[version]/
- 3. Build node.js; instructions that may assist are available at github
- 4. Ensure that nodejs is in the \$PATH. One method is to use a symlink from the installation: ln -s /opt/node-[version]/bin/node

Hadoop/HBase Environment

For a distributed enterprise, you must install these Hadoop components:

| Component | Distribution | Required Version |
|-----------|-------------------|---------------------------|
| HDFS | Apache Hadoop DFS | 2.0.2-alpha or later |
| | CDH | 4.2.x or later |
| | HDP | 2.0 or later |
| YARN | Apache Hadoop DFS | 2.0.2-alpha or later |
| | CDH | 4.2.x or later |
| | HDP | 2.0 or later |
| HBase | | 0.94.2+, 0.96.0+, 0.98.0+ |
| Zookeeper | | Version 3.4.3 or later |
| Hive | | Version 12.0 or later |
| | CDH | 4.3.x or later |
| | HDP | 2.0 or later |

Reactor nodes require Hadoop and HBase client installation and configuration. No Hadoop services need to be running.

Certain Continuuity components need to reference your *Hadoop*, *HBase*, *YARN* (and possibly *Hive*) cluster configurations by adding your configuration to their classpaths.

Prepare the Cluster

To prepare your cluster so that Continuuity Reactor can write to its default namespace, create a top-level /continuuity directory in HDFS, owned by an HDFS user yarn:

```
hadoop fs -mkdir /continuuity && hadoop fs -chown yarn /continuuity
```

In the Continuuity Reactor packages, the default HDFS namespace is /continuuity and the default HDFS user is yarn. If you set up your cluster as above, no further changes are required.

To make alterations to your setup, create an .xml file conf/continuuity-site.xml (see the Appendix) and set appropriate properties.

- If you want to use an HDFS directory with a name other than /continuuity:
 - 1. Create the HDFS directory you want to use, such as /myhadoop/myspace.
 - 2. Create an hdfs.namespace property for the HDFS directory in conf/continuuity-site.xml:

- 3. Ensure that the default HDFS user yarn owns that HDFS directory.
- If you want to use a different HDFS user than yarn:
 - 1. Check that there is—and create if necessary—a corresponding user on all machines in the cluster on which YARN is running (typically, all of the machines).
 - 2. Create an hdfs.user property for that user in conf/continuuity-site.xml:

- 3. Check that the HDFS user owns the HDFS directory described by hdfs.namespace on all machines.
- To use the ad-hoc querying capabilities of Reactor, enable the Reactor Explore Service in conf/continuuity-site.xml (by default, it is disabled):

Note that this feature is currently not supported on secure Hadoop clusters.

Secure Hadoop

When running Continuuity Reactor on top of Secure Hadoop and HBase (using Kerberos authentication), the Reactor Master process will need to obtain Kerberos credentials in order to authenticate with Hadoop and HBase. In this case, the setting for hdfs.user in continuuity-site.xml will be ignored and the Reactor Master process will be identified as the Kerberos principal it is authenticated as.

In order to configure Reactor Master for Kerberos authentication:

- Create a Kerberos principal for the user running Reactor Master.
- Install the k5start package on the servers where Reactor Master is installed. This is used to obtain Kerberos credentials for Reactor Master on startup.
- Generate a keytab file for the Reactor Master Kerberos principal and place the file in /etc/security/keytabs/continuuity.keytab on all the Reactor Master hosts. The file should be readable only by the user running the Reactor Master process.
- Edit /etc/default/continuuity-reactor-master:

```
REACTOR_KEYTAB="/etc/security/keytabs/continuuity.keytab"
REACTOR_PRINCIPAL="<reactor principal>@EXAMPLE.REALM.COM"
```

• When Reactor Master is started via the init script, it will now start using k5start, which will first login using the configured keytab file and principal.

ULIMIT Configuration

When you install the Continuuity Reactor packages, the ulimit settings for the Continuuity user are specified in the /etc/security/limits.d/continuuity.conf file. On Ubuntu, they won't take effect unless you make changes to the /etc/pam.d/common-session file. For more information, refer to the ulimit discussion in the Apache HBase Reference Guide.

Packaging

Continuuity components are available as either Yum .rpm or APT .deb packages. There is one package for each Continuuity component, and each component may have multiple services. Additionally, there is a base Continuuity package with two utility packages installed which creates the base configuration and the continuuity user. We provide packages for *Ubuntu 12* and *CentOS 6*.

Available packaging types:

RPM: YUM repoDebian: APT repo

• Tar: For specialized installations only

Continuuity packages utilize a central configuration, stored by default in /etc/continuuity.

When you install the Continuuity base package, a default configuration is placed in /etc/continuuity/conf.dist. The continuuity-site.xml file is a placeholder where you can define your specific configuration for all Continuuity components.

Similar to Hadoop, Continuuity utilizes the alternatives framework to allow you to easily switch between multiple configurations. The alternatives system is used for ease of management and allows you to to choose between different directories to fulfill the same purpose.

Simply copy the contents of /etc/continuuity/conf.dist into a directory of your choice (such as /etc/continuuity/conf.myreactor) and make all of your customizations there. Then run the alternatives command to point the /etc/continuuity/conf symlink to your custom directory.

RPM using Yum

Create a file continuuity.repo at the location:

/etc/yum.repos.d/continuuity.repo

The RPM packages are accessible using Yum at this authenticated URL:

[continuuity]
name=Continuuity Reactor Packages
baseurl=https://<username>:<password>@repository.continuuity.com/content/groups/restricted
enabled=1
protect=0
gpgcheck=0
metadata_expire=30s
autorefresh=1
type=rpm-md

where: <username>: Username provided by your Continuuity.com representative

<password>: Password provided by your Continuuity.com representative

Debian using APT

Debian packages are accessible via APT on Ubuntu 12.

Create a file continuuity.list at the location:

```
/etc/apt/sources.list.d/continuuity.list
```

Use this authenticated URL (on one line):

deb [arch=amd64] https://<username>:<password>@repository.continuuity.com/content/sites/apt
 precise release

where: <username>: Username provided by your Continuuity.com representative

<password>: Password provided by your Continuuity.com representative

Installation

Install the Continuuity Reactor packages by using either of these methods:

Using Yum (on one line):

Using APT (on one line):

Do this on each of the boxes that are being used for the Reactor components; our recommended installation is a minimum of two boxes.

This will download and install the latest version of Continuuity Reactor with all of its dependencies. When all the packages and dependencies have been installed, you can start the services on each of the Reactor boxes by running this command:

```
for i in `ls /etc/init.d/ | grep continuuity` ; do service $i restart ; done
```

When all the services have completed starting, the Continuuity Web-App should then be accessible through a browser at port 9999. The URL will be <app-fabric-ip>:9999 where <app-fabric-ip> is the IP address of one of the machine where you installed the packages and started the services.

Upgrading From a Previous Version

When upgrade an existing Continuuity Reactor installation from a previous version, you will need to make sure the Reactor table definitions in HBase are up-to-date.

These steps will stop Reactor, update the installation, run an upgrade tool for the table definitions, and then restart Reactor.

1. Stop all Continuuity Reactor processes:

```
for i in `ls /etc/init.d/ | grep continuuity` ; do service $i stop ; done
```

- 2. Update the Continuuity Reactor packages by running either of these methods:
 - Using Yum (on one line):

```
sudo yum install continuuity continuuity-gateway

continuuity-hbase-compat-0.94 continuuity-hbase-compat-0.96

continuuity-kafka continuuity-reactor-master

continuuity-security continuuity-web-app
```

• Using APT (on one line):

```
sudo apt-get install continuuity continuuity-gateway
continuuity-hbase-compat-0.94 continuuity-hbase-compat-0.96
continuuity-kafka continuuity-reactor-master
continuuity-security continuuity-web-app
```

3. Run the upgrade tool (on one line):

```
/opt/continuuity/reactor-master/bin/svc-reactor-master run com.continuuity.data.tools.ReactorTool upgrade
```

4. Restart the Continuuity Reactor processes:

```
for i in `ls /etc/init.d/ | grep continuuity`; do service $i start; done
```

Verification

To verify that the Continuuity software is successfully installed and you are able to use your Hadoop cluster, run an example application. We provide in our SDK pre-built .JAR files for convenience:

- 1. Download and install the latest Continuuity Developer Suite from http://accounts.continuuity.com.
- 2. Extract to a folder (CONTINUUITY HOME).
- 3. Open a command prompt and navigate to CONTINUUITY_HOME/examples.
- 4. Each example folder has in its target directory a .JAR file. For verification, we will use the TrafficAnalytics example.
- 5. Open a web browser to the Continuuity Reactor Web-App ("Dashboard"). It will be located on port 9999 of the box where you installed Reactor.
- 6. On the Dashboard, click the button Load an App.
- 7. Find the pre-built JAR (*TrafficAnalytics-1.0.jar*) by using the dialog box to navigate to CONTINUUITY_HOME/examples/TrafficAnalytics/target/TrafficAnalytics-1.0.jar
- 8. Once the application is deployed, instructions on running the example can be found at the TrafficAnalytics example.
- 9. You should be able to start the application, inject log entries, run the MapReduce job and see results.
- 10 When finished, stop and remove the application as described in the TrafficAnalytics example.

.

Troubleshooting

Here are some selected examples of potential problems and possible resolutions.

Application Won't Start

Check HDFS write permissions. It should show an obvious exception in the YARN logs.

No Metrics/logs

Make sure the *Kafka* server is running, and make sure local the logs directory is created and accessible. On the initial startup, the number of available seed brokers must be greater than or equal to the *Kafka* default replication factor.

In a two-box setup with a replication factor of two, if one box fails to startup, metrics will not show up though the application will still run:

```
[2013-10-10 20:48:46,160] ERROR [KafkaApi-1511941310]
Error while retrieving topic metadata (kafka.server.KafkaApis)
kafka.admin.AdministrationException:
replication factor: 2 larger than available brokers: 1
```

Only the First Flowlet Showing Activity

Check that YARN has the capacity to start any of the remaining containers.

YARN Application Shows ACCEPTED For Some Time But Then Fails

It's possible that YARN can't extract the .JARs to the /tmp, either due to a lack of disk space or permissions.

Log Saver Process Throws an Out-of-Memory Error, Reactor Dashboard Shows Service Not OK

The Continuuity Reactor Log Saver uses an internal buffer that may overflow and result in Out-of-Memory Errors when applications create excessive amounts of logs. One symptom of this is that the Reactor Dashboard Services Explorer shows the log.saver Service as not OK, in addition to seeing error messages in the logs.

By default, the buffer keeps 8 seconds of logs in memory and the Log Saver process is limited to 1GB of memory. When it's expected that logs exceeding these settings will be produced, increase the memory allocated to the Log Saver or increase the number of Log Saver instances. If the cluster has limited memory or containers available, you can choose instead to decrease the duration of logs buffered in memory. However, decreasing the buffer duration may lead to out-of-order log events.

In the continuuity-site.xml, you can:

- Increase the memory by adjusting log.saver.run.memory.megs;
- Increase the number of Log Saver instances using log.saver.num.instances; and
- Adjust the duration of logs with log.saver.event.processing.delay.ms.

Note that it is recommended that log.saver.event.processing.delay.ms always be kept greater than log.saver.event.bucket.interval.ms by at least a few hundred (300-500) milliseconds.

| See the log.saver parameter values that can be adjusted. | section | of the | Appendix | x for a li | ist of these | configuration | parameters | and their |
|--|---------|--------|----------|------------|--------------|---------------|------------|-----------|
| | | | | | | | | |
| | | | | | | | | |
| | | | | | | | | |
| | | | | | | | | |
| | | | | | | | | |
| | | | | | | | | |
| | | | | | | | | |
| | | | | | | | | |
| | | | | | | | | |
| | | | | | | | | |
| | | | | | | | | |
| | | | | | | | | |
| | | | | | | | | |
| | | | | | | | | |
| | | | | | | | | |
| | | | | | | | | |
| | | | | | | | | |
| | | | | | | | | |
| | | | | | | | | |
| | | | | | | | | |
| | | | | | | | | |

Appendix: continuuity-site.xml

Here are the parameters that can be defined in the continuuity-site.xml file, their default values, descriptions and notes.

For information on configuring the continuuity-site.xml file and Reactor for security, see the online document Reactor Security Guide.

| Parameter name | Default Value | Description |
|------------------------------------|---|--|
| app.bind.address | 127.0.0.1 | App-Fabric server host address |
| app.bind.port | 45000 | App-Fabric server port |
| app.command.port | 45010 | App-Fabric command port |
| app.output.dir | /programs | Directory where all archives are stored |
| app.program.jvm.opts | <pre>\${weave.jvm.gc.opts}</pre> | Java options for all program containers |
| app.temp.dir | /tmp | Temp directory |
| dashboard.bind.port | 9999 | Dashboard bind port |
| data.local.storage | \${local.data.dir}/ldb | Database directory |
| data.local.storage.blocks ize | 1024 | Block size in bytes |
| data.local.storage.caches ize | 104857600 | Cache size in bytes |
| data.queue.config.update. interval | 5 | Frequency, in seconds, of updates to the queue consumer |
| data.queue.table.name | queues | Tablename for queues |
| data.tx.bind.address | 127.0.0.1 | Transaction Inet address |
| data.tx.bind.port | 15165 | Transaction bind port |
| data.tx.client.count | 5 | Number of pooled transaction instances |
| data.tx.client.provider | thread-local | Provider strategy for transaction clients |
| data.tx.command.port | 15175 | Transaction command port number |
| data.tx.janitor.enable | True | Whether or not the TransactionDataJanitor coprocessor |
| data.tx.server.io.threads | 2 | Number of transaction IO threads |
| data.tx.server.threads | 25 | Number of transaction threads |
| data.tx.snapshot.dir | <pre>\${hdfs.namespace}/tx.snapshot</pre> | Directory in HDFS used to store snapshots and transaction logs |
| data.tx.snapshot.interval | 300 | Frequency of transaction snapshots in seconds |

| data.tx.snapshot.local.di | \${local.data.dir}/tx.snapshot | Snapshot storage directory on the local filesystem |
|--|--------------------------------|---|
| data.tx.snapshot.retain | 10 | Number of retained transaction snapshot files |
| enable.unrecoverable.rese t | False | WARNING: Enabling this option makes it possible to delete all applications and data; no recovery is possible! |
| explore.active.operation. timeout.secs | 86400 | Timeout value in seconds for a SQL operation whose result is not fetched completely |
| explore.cleanup.job.sched ule.secs | 60 | Time in secs to schedule clean up job to timeout operations |
| explore.executor.containe r.instances | 1 | Number of explore executor instances |
| explore.executor.max.inst ances | 1 | Maximum number of explore executor instances |
| explore.inactive.operatio n.timeout.secs | 3600 | Timeout value in seconds for a SQL operation which has no more results to be fetched |
| gateway.boss.threads | 1 | Number of Netty server boss threads |
| gateway.connection.backlo | 20000 | Maximum connection backlog of Gateway |
| gateway.exec.threads | 20 | Number of Netty server executor threads |
| gateway.max.cached.events .per.stream.num | 5000 | Maximum number of a single stream's events cached before flushing |
| <pre>gateway.max.cached.stream .events.bytes</pre> | 52428800 | Maximum size (in bytes) of stream events cached before flushing |
| <pre>gateway.max.cached.stream .events.num</pre> | 10000 | Maximum number of stream events cached before flushing |
| gateway.memory.mb | 2048 | Memory in MB for Gateway process in YARN |
| gateway.num.cores | 2 | Cores requested per Gateway container in YARN |
| gateway.num.instances | 1 | Number of Gateway instances in YARN |
| gateway.server.address | localhost | Router address to which Dashboard connects |
| gateway.server.port | 10000 | Router port to which Dashboard connects |

| gateway.stream.callback.e xec.num.threads | 5 | Number of threads in stream events callback executor |
|---|-------------------------|---|
| gateway.stream.events.flu sh.interval.ms | 150 | Interval at which cached stream events get flushed |
| gateway.worker.threads | 10 | Number of Netty server worker threads |
| hdfs.lib.dir | \${hdfs.namespace}/lib | Common directory in HDFS for JAR files for coprocessors |
| hdfs.namespace | /\${reactor.namespace} | Namespace for files written by Reactor |
| hdfs.user | yarn | User name for accessing HDFS |
| hive.local.data.dir | \${local.data.dir}/hive | Location of hive relative to local.data.dir |
| hive.server.bind.address | localhost | Router address hive server binds to |
| kafka.bind.address | 0.0.0.0 | Kafka server hostname |
| kafka.bind.port | 9092 | Kafka server port |
| kafka.default.replication .factor | 1 | Kafka replication factor [Note 1] |
| kafka.log.dir | /tmp/kafka-logs | Kafka log storage directory |
| kafka.num.partitions | 10 | Default number of partitions for a topic |
| kafka.seed.brokers | 127.0.0.1:9092 | Kafka brokers list (comma separated) |
| kafka.zookeeper.namespace | continuuity_kafka | Kafka Zookeeper namespace |
| local.data.dir | data | Data directory for local mode |
| log.base.dir | /logs/avro | Base log directory |
| log.cleanup.run.interval. | 1440 | Log cleanup interval in minutes |
| log.publish.num.partition | 10 | Number of Kafka partitions to publish the logs to |
| log.retention.duration.da | 7 | Log file HDFS retention duration in days |
| log.run.account | continuuity | Logging service account |
| log.saver.event.bucket.in terval.ms | 4000 | Log events published in this interval (in milliseconds) will be processed in a batch. Smaller values will increase the odds of log events going out-of-order. |

| log.saver.event.processin g.delay.ms | 8000 | Buffer log events in memory for given time, in milliseconds. Log events received after this delay will show up out-of-order. This needs to be greater than log.saver.even t.bucket.interval.ms by at least a few hundred milliseconds. |
|--|---------------------------------------|--|
| log.saver.num.instances | 1 | Log Saver instances to run in YARN |
| log.saver.run.memory.megs | 1024 | Memory in MB allocated to the Log Saver process |
| metadata.bind.address | 127.0.0.1 | Metadata server address |
| metadata.bind.port | 45004 | Metadata server port |
| metadata.program.run.hist ory.keepdays | 30 | Number of days to keep metadata run history |
| metrics.data.table.retent ion.resolution.1.seconds | 7200 | Retention resolution of the 1 second table in seconds |
| metrics.kafka.partition.s ize | 10 | Number of partitions for metrics topic |
| metrics.query.bind.addres | 127.0.0.1 | Metrics query server host address |
| metrics.query.bind.port | 45005 | Metrics query server port |
| reactor.explore.enabled | false | Determines if the Reactor Explore Service is enabled |
| reactor.namespace | continuuity | Namespace for this Reactor instance |
| router.bind.address | 0.0.0.0 | Router server address |
| router.client.boss.thread | 1 | Number of router client boss threads |
| router.client.worker.thre ads | 10 | Number of router client worker threads |
| router.connection.backlog | 20000 | Maximum router connection backlog |
| router.forward.rule | 10000:gateway,20000:webapp/\$HO ST | Router forward rules [Note 2] |
| router.server.boss.thread | 1 | Number of router server boss threads |
| router.server.worker.thre ads | 10 | Number of router server worker threads |
| scheduler.max.thread.pool .size | 30 | Size of the scheduler thread pool |
| security.auth.server.addr | 127.0.0.1 | IP address that the Continuuity Authentication Server should listen on. |

| security.auth.server.port | 10009 | Port number that the Continuuity Authentication Server should bind |
|--|---|--|
| | | to for HTTP. |
| security.authentication.b asic.realmfile | | Username / password file to use when basic authentication is configured |
| security.authentication.h andlerClassName | | Name of the authentication implementation to use to validate user credentials |
| security.authentication.l oginmodule.className | | JAAS LoginModule implementation to use when com.continuuity.se curity.server.JAASAuthenticati onHandler is configured for security.authentication.handlerClass |
| security.data.keyfile.pat | <pre>\${local.data.dir}/security/key file</pre> | Path to the secret key file (only used in single-node operation) |
| security.enabled | false | Enables authentication for Reactor. When set to true all requests to Reactor must provide a valid access token. |
| security.realm | continuuity | Authentication realm used for scoping security. This value should be unique for each installation of Continuuity Reactor. |
| security.server.extended. token.expiration.ms | 604800000 | Admin tool access token expiration time in milliseconds (defaults to 1 week) (internal) |
| security.server.maxthread | 100 | Maximum number of threads that the Continuuity Authentication Server should use for handling HTTP requests. |
| security.server.ssl.enabl | false | Set to true to enable use of SSL on the Continuuity Authentication Server |
| security.server.ssl.keyst ore.password | | Password to the Java keystore file specified in security.server.ssl .keystore.path |
| security.server.ssl.keyst ore.path | | Path to the Java keystore file containing the certificate used for HTTPS on the Continuuity Authentication Server. |
| security.server.ssl.port | 10010 | Port to bind to for HTTPS on the Continuuity Authentication Server. |
| security.server.token.exp iration.ms | 86400000 | Access token expiration time in milliseconds (defaults to 24 hours) |

| security.token.digest.alg | HmacSHA256 | Algorithm used for generating MAC of access tokens |
|--|---|---|
| security.token.digest.key .expiration.ms | 3600000 | Time duration (in milliseconds) after which an active secret key used for signing tokens should be retired |
| security.token.digest.key length | 128 | Key length used in generating the secret keys for generating MAC of access tokens |
| security.token.distribute d.parent.znode | <pre>/\${reactor.namespace}/security /auth</pre> | Parent node in ZooKeeper used for secret key distribution in distributed mode. |
| stream.flume.port | 10004 | |
| stream.flume.threads | 20 | |
| thrift.max.read.buffer | 16777216 | Maximum read buffer size in bytes used by the Thrift server [Note 3] |
| weave.java.reserved.memor y.mb | 250 | Reserved non-heap memory in MB for Weave container |
| weave.jvm.gc.opts | -verbose:gc -Xloggc: <log-dir>/gc.log -XX:+PrintGCDetails -XX:+PrintGCTimeStamps -XX:+UseGCLogFileRotation -XX:NumberOfGCLogFiles=10 -XX:GCLogFileSize=1M</log-dir> | Java garbage collection options for all Weave containers; <log-dir> is the location of the log directory on each machine</log-dir> |
| weave.no.container.timeou t | 120000 | Amount of time in milliseconds to wait for at least one container for Weave runnable |
| weave.zookeeper.namespace | /weave | Weave Zookeeper namespace prefix |
| yarn.user | yarn | User name for running applications in YARN |
| zookeeper.quorum | 127.0.0.1:2181/\${reactor.names pace} | Zookeeper address host:port |
| zookeeper.session.timeout .millis | 40000 | Zookeeper session time out in milliseconds |

- Note 1: kafka.default.replication.factor is used to replicate *Kafka* messages across multiple machines to prevent data loss in the event of a hardware failure. The recommended setting is to run at least two *Kafka* servers. If you are running two *Kafka* servers, set this value to 2; otherwise, set it to the number of *Kafka* servers
- Note 2: This configuration has two rules:
 - 1. Forward anything that comes on port 10000 to the service Gateway.
 - 2. Forward anything that comes on port 20000 to webapp/\$HOST, where \$HOST is the host that the webapp wants to impersonate.

Example: webapp/streamy.com points to a webapp container running in YARN, with DNS set to point *streamy.com* to the router host. The router then forwards it to the webapp container in YARN.

Note 3: Maximum read buffer size in bytes used by the Thrift server: this value should be set to greater than the maximum frame sent on the RPC channel.