UNIVERSITY OF PFORZHEIM SCHOOL OF ENGINEERING

MASTER PROGRAM EMBEDDED SYSTEMS

MASTER THESIS

The Zircon Kernel A Consideration of a Microkernel Approach and its Effects on Driver Development

Examiner
Second Supervisor
Author
Matriculation Number

Prof. Dr.-Ing. Rainer Dietz Prof. Dr.-Ing. Martin Pfeiffer B.Sc. Anna-Lena Marx 317593

Submission Date

20.06.2019

Eidesstattliche Erklärung

Ich erkläre hiermit, dass ich die vorliegende Master-Thesis selbstständig, ohne Hilfe Dritter und ohne Benutzung anderer als der angegebenen Hilfsmittel angefertigt habe. Die aus fremden Quellen direkt oder indirekt übernommenen Gedanken sind als solche kenntlich gemacht. Die Arbeit wurde bisher in gleicher oder ähnlicher Form keiner anderen Prüfungsbehörde vorgelegt und auch nicht veröffentlicht.

Pforzheim, den 20. Juni 2019

Contents

1	Int r 1.1	roduction Research Objectives					
2	Modern Operating System Concepts						
	2.1	Opera	ting System Architectures				
		2.1.1	Monolithic Architectures				
		2.1.2	Microkernel Architectures				
		2.1.3	Layered Architectures				
		2.1.4	Hybrid Architectures				
		2.1.5	The Linux Kernel's Monolithic Architecture				
		2.1.6	The Zircon Kernel's Microkernel Architecture				
	2.2	System	n Calls				
		2.2.1	System Calls in Linux				
		2.2.2	System Calls in Zircon				
	2.3	Proces	sses and Threads				
		2.3.1	Processes				
		2.3.2	Threads				
		2.3.3	Processes and Threads in Linux				
		2.3.4	Processes and Threads in Zircon				
	2.4	Synch	ronization and Inter Process Communication				
		2.4.1	Synchronization				
		2.4.2	Inter Process Communication				
		2.4.3	Synchronization and IPC in Linux				
		2.4.4	Synchronization and IPC in Zircon				
	2.5	Sched	uling $\dots \dots \dots$				
		2.5.1	Scheduling in Linux				
		2.5.2	Scheduling in Zircon				
	2.6	Memo	ry Management				
		2.6.1	Address Space				
		2.6.2	Virtual Memory				
		2.6.3	Memory Management in Linux				
		2.6.4	Memory Management in Zircon				
	2.7	I/O .					
		2.7.1	I/O Hardware				

vi *CONTENTS*

5	Conclusion							
4								
	3.5	Evalua	ation					
			11					
		3.4.2	PDev Driver					
		3.4.1	Driver					
	3.4	Zircon						
		3.3.1	Driver Implementation					
	3.3							
	3.2		al Driver Concept					
		3.1.1	Hardware Issues					
	3.1	Test Se	etup					
3	Case Study: Driver Development in Linux and Zircon							
	2.8	Driver	Models	•				
		2.7.5	Power Management					
		2.7.4	Interrupts					
		2.7.3	Direct Memory Access					
		2.7.2	Memory Mapped IO					

Chapter 1

Introduction

Modern application Central Processing Units (CPUs), as used for e.g. desktop computers or smartphones, are highly complex ciruits consisting of at least two independent actual processing units. It is hardly possible to master these multicore processors, associated memory and Input/Output (I/O) devices in their full complexity nor take advantage of their actual computing power or security mechanisms without using an operating system as an abstraction layer between the actual hardware and its user. As such an operating system, to manage a computer's physical resources and share them between an amount of user programs in a fair and safe way, is the central task. The part of operating systems providing this task is commonly referred as the kernel. Even if this distinction is widely uses, especially for Linux, there is hardly no clear and global definition which specific tasks of an operating system are part of the kernel. Albrecht Achilles named process management, memory management and basic I/O operations as such ones in his book 1. Actually, this distinction between a whole operating system and its kernel itself is that hard because it is not even consistent between different operating system architecture concepts. The lot of different goals and use-cases for operating systems which have a big impact to the architectual design, and with this to the term kernel too. But for a majority of them, at least the central device drivers are considered as part of the kernel.

With Linux and Fuchsia, two fundamentally different representatives of the two best-known operating system concepts will be considered in this work, the monolith and the microkernels. Fuchsia, respectively Zircon, as the kernel is named, is a new microkernel operating system which is developed from scratch by Google. The project is developed in public since 2016¹, but since it gone public, there has been no official announcement about the purpose of the system. Nevertheless, there are lots of reasons to study Fuchsia and especially to its kernel Zircon. The first one is clearly an architectual one, as Zircon is a microkernel. Of course are there some industrial used microkernel architectures, but the most and most successful ones are Portable Operating System Interface for UniX (POSIX) compatible and targeting real time tasks, such as QNX or FreeRTOS. But apart from the unknown use-case, Zircon differs in this very important aspect, the

¹androidpolice.com, visited on 13.02.2019 https://www.androidpolice.com/2016/08/12/google-developing-new-fuchsia-os-also-likes-making-new-words/

POSIX compatibility which provides a global standard (DIN 9945, IEEE1003.2) for UNIX-like operating systems[48]. That is a very brave decision as POSIX compatibility is a common part of public tenders for software. Beside this, one further point making Zircon an interesting research topic is C++ as preferred programming language for the kernel, which is a rather unsual choice[45].

Linux is in many issues very opposite to Zircon. It was started as a hobby project by Linus Torvalds in 1991 and growed over the years to a widely spread, powerful kernel. Today, it is, due to its use in Android, the most used operating system kernel at all². Since Linux was published, it is actively developed by a divers community and is not subject to the interests of a single company. Presumably, that is a powerful factor for its spread besides its licensing. Nevertheless, Linux is a grown software project. Architectural decisions, for example the one for its implementation as a monolithic kernel and its relation to UNIX, are based in the very beginnings of Linux as a personal hobby project and affect it still today. In a well-known mailing list discussion with Andrew S. Tanenbaum in 1992, Torvalds even admit the theoretical superiority of microkernels over monolithic ones[46]. But some years later, in 2006, the Linux contributer Richard Gooch justified the question why Linux won't change to a microkernel architecture with performance drawbacks of them compared to monolithic ones due to privilege barriers[16].

Along with the guess Zircon will target the same sector as Linux, especially the mobile and embedded sector, both of them make an interesting comparison to examine the impacts of kernel concepts to an essential part of them, the device driver development. In this process, the date of origin should be concerned as an additional factor. It it to be assumed the Zircon team is aware to especially historical based, rather poor decisions in Linux and other operating systems, and seizes the chance of a completely new product.

1.1 Research Objectives

This work's aim is to evaluate the differences between monolithic and microkernel architectures for operating systems and how they influence the development of device drivers. For this purpose, this work shall focus only on the operating system's kernels, the Zircon kernel and the Linux kernel. In most of literature, filesystems are also listed as an essential part of an operating system, but shall be unattended in this work. Of course they are essential, but there exist that much different concepts and implementations for filesystems to form an own research. For this particular work is the specific filesystem implementation not crucial due to the focus on kernel and device drivers. As a result, the operating systems top layers, neighter Google's Fuchsia in its entirety nor the Linux userland or desktop environments shall be a part of this thesis.

Contrarily, the following topics are to be examined within the scope of this work:

• Introducing basic concepts of operating system kernels and examine how they

²netmarkedshared.com, visited on 13.02.2019 https://bit.ly/2S0s4lM

are implemented in the specific realizations, Linux and Zircon.

- Examining the effects of the architectural differences of the two well-known approaces *monolithic* and *microkernel* on device driver development using the example of the non academic, specific implementations, *Linux* and *Zircon*. This includes:
 - The analysis of the driver models and how they are integrated to the kernel.
 - Examining the driver development itself on both architectures with the aid of a hands-on case study.
 - The inspection of the driver development workflow, especially with a view on available tooling.
 - A consideration on the way the drivers are used by the kernel itself, especially
 by other kernel components, and the actual users.
- Evaluating the results of this examinations based on the theoretical concepts and its actual realizations with respect to the temporal evoluting of *Linux* and *Zircon*.

Chapter 2

Modern Operating System Concepts

This thesis' introduction already picked up the discussion about which operating system architecture is the superior one by referring to the Tanenbaum-Torvalds debate [46] in 1992. Besides the discussion is quite interessting from todays view on different operating systems, the forecasts on their future and the actual development, are both, TANENBAUM and TORVALDS underpinning their arguments with the origins of their implementations MINIX and Linux in different problems. And roughly spoken are exactly such different problems which needs to be solved with an operating system one reason for their diversity. Over the years, they had to fit in solving very different kinds of problems on very different kinds of hardware, which resulted in many different ways of working and architectures. As with the debate, it is rather difficult to impossible to find one architectural concept or implementation which is clearly superior to the other ones in every use-case. Nevertheless, it is a reasonable question why a majority of the operating system kernels which were developed from scratch in the last few years are based on a microkernel concept. In 2009, the official statement of the Linux kernel developer RICHARD GOOCH was still that monolithic kernels are superior for performance reasons[16]. So the question remains what changed during the last ten years to promote this change, and especially for this work, how this affects on device driver development. For this reason, this chapter is dedicted to the basic components and functionallities of operating system kernels and how they are implemented in the real world examples *Linux* and *Zircon*.

2.1 Operating System Architectures

As already pointed out are architectural decisions for operating systems commonly influenced by the issues they are intended to solve. By giving priority to some design objectives that are pertinent to the underlying issue, different concepts and architectures are the outcome. According to GLATZ[15] are some of them:

- Providing a reliable, crash-proof environment.
- Providing a portable operating system.

- Providing a scalable operating system, e.g. in terms of processing cores.
- Providing an extensibile operating system, e.g. in terms of adding additional functionality to the kernel.
- Providing real-time capabilities.
- Providing an efficient design in terms of ressources and performance.
- Providing a secure environment for user applications.
- Providing a maintainable operating system, e.g. by the division of policy and mechanism.

In addition, operating systems should also pay attention to the common software design issue mechanism vs. policy. That means an operating system design should provide a clear distinction between the mechanism, that means the capable abilities that can be performed (how is something done) and the policy, which controlls how the available capabilities are used (what is done)[24], [39]. An example for driver development could be controlling the number of processes that can use a device at once. In this case, the driver should provide the mechanism, the how such a limitation could be done, but not what, the actual number of allowed processes. The idea behind is that requirements may change over some time and such a distinction makes it easy to adjust the policy via some parameters without touching the underlying mechanism[39].

How these design principles fit into the known operating system architectures will be considered in the following sections. But before, the terms *kernel mode* and *user mode* will be explained as they are fundamental for this work.

Dual-Mode Execution

Modern general purpose CPUs provide a ring based, hardware enabled security model which had it's origin in the Intel x86 processor architecture[45]. It is usually made of four different security levels, the rings 0 to 3 which are illustrated in Figure 2.1. In this theoretical model, ring 3 is the least secure level, used for common user applications (even if started with extended privileges (root for the UNIX-like world)), while ring 2 is used for libraries shared between user applications and ring 1 is for system calls[15]. Actual operating system implementations may not use all of them. Linux for example utilize ring 3 for user-space applications, shared libraries and ring 0 for system calls and the kernel. System calls provide the transition to ring 0, the one with the topmost security level, which is used for the operating system kernel. Actual operating system implementations may not use all of them. Linux for example utilize ring 3 for user-space applications, shared libraries and ring 0 for system calls and the kernel. As a crucial part of an operating system, system calls will be discussed in more detail later in this work.

Directly related to this model is the *dual-mode* execution mode of modern CPUs. It is a hardware enabled security concept to provide a distinction between the user

applications in ring 3 and the actual operating system kernel in ring 0. Just the kernel in ring 0, running in the kernel mode (or privileged mode, supervisor mode or system mode), has direct and privileged access to memory, hardware, timers or interrupts, e.g. for performing I/O operatings or memory mappings[24]. User applications in ring 3, running in the user mode, are not allowed to them so directly, they have limited privileges and a limited instruction set. As named above, they need to use a mechanism called system calls to transfer the execution to the kernel mode where the priviledged actions are performed. Lastly, the execution is transfered back to the calling user process and with this, the mode changes back to user mode. Figure 2.2 pictures the operating flow of a system call including the mode switches between user and kernel mode.




Figure 2.1: The Rings of the x86's security concept[15]




Figure 2.2: A system calls sequence including the mode switches[15]

The CPU's operating mode is usually controlled by a specific bit in the Program Status Word (PSW)[45]. PSW is term on x86 CPU architectures. It is corresponding to the Current Program Status Register (CPSR) on ARM architectures¹. But since in literature is always spoken of the PSW regardless of the concrete CPU's architecture, this should also be done in this work. It influences the state of each CPU core itself in a

 $^{^{1}} http://infocenter.arm.com, visited on 08.03.2019$ http://infocenter.arm.com/help/index.jsp?topic=/com.arm.doc.dui0473f/CHDFAEID.html

multi-processor system, but not the operating system kernel. As a result, different CPU cores may be in a different execution mode[24]. With this separation, any priviledged instruction is forbidden in *user mode* and will not be executed.

Based on the dual mode execution on the CPU, different architectural concepts for operating systems evolved. They differ e.g. in the share of the operating system respectively the operating system's kernel actually running within the CPU's kernel mode. Thus, they have an influence on the whole system, including device driver development but also on performance and security issues.

With this basic knowledge about the CPU's operating modes, the next section researches a selection of different operating system architectures. Special attention should be paid to the most common ones, the monolithic and the microkernel architectures and their implementation in Linux and Zircon. On the contrary, this work will not take a particular look on special purpose operating system architectures such as ones for loosely coupled multi-processor systems known from processing clusters. Today, even the majority of general purpose computing systems are driven by more than one CPU cores and most of common modern operating systems are designed to provide support for the defacto standard for tightly coupled systems, Symmetric Multiprocessing (SMP).

2.1.1 Monolithic Architectures

Some sources, such as GLATZ[15] or SILBERSCHATZ[39], suggest monolithic operating systems do not have a well-defined structure at all. As they are indeed most commonly grown structures, started in a completely different scope (MS-DOS, the original UNIX), it is not an incorrect claim. But it does not necessarily have to be the case. Above all, monolithic operating system (kernel) architectures have in common that they form one single binary program which is running entirely in kernel mode. User programms, running in user mode, interact with the kernel only through a well defined set of system calls [24]. Within the kernel itself, all parts are free to use and access each other but also the hardware, without any limitation, e.g. regarging the access of kernel functionalities of another component or hardware acces. That means a function or procedure initial developed for scheduling processes could be used in a completely different context if its functionality is useful to solve another issue. In fact, there is no information hiding between kernel functions or procedures. Any function in this kernel context has full access to the hardware, such as I/O devices, timers, interrupts and even to the memory. There is no memory protection or validation between different components of a monolithic kernel. Of course, this leads to some serious disadvantages in this architecture, for example could a crash in one single function or procedure crash the entire kernel or the resulting system may become difficult to understand and maintain [45], [39]. The missing memory protecting within the kernel could also be a source for crashes or attacks. But in contrast, this design also enables a very efficient kernel design without any unneeded communication overhead or hardware inefficiencies [24].

An extension of the monolithic architecture are the so-called **modular operating**

systems. They provide additional, defined interfaces for (in common) dynamically loadable and unloadable extentions, e.g. for device drivers or filesystems. Sometimes, such extensions or modules are just allowed to use a limited function set of the operating system, but they are still running as a part of the kernel in kernel mode[24], [45]. Just like ordinary kernel functions or procedures, (malicious) programming errors in extentions may lead to a kernel crash or manipulate or damage other components. Contrary, the modular concept provides some advantages over regular monolitic kernels. It allows to slim down the actual kernel by providing the chance to reload only the actually needed functionality dynamically and e.g. security patches within such an extension is possible without restarting the entire system[5]. As the extensions become an part of the operating system running in kernel mode, no additional communication effort between the actual kernel and the modules is required. Thus, concept of modules is quite popular for basically monolithic operating systems like Linux or Solaris[5], [39].

2.1.2 Microkernel Architectures

The microkernel architecture focuses on very opposite design goals compared to the monolithic one. Some of them are to cope the complexity, rather poor maintainablity and susceptibility to errors by a massively modular approach. To archive this, the core idea behind microkernels is to provide only a very small kernel running in kernel mode which only provides the core functionalities while all the other important functions of an operating system are running in user mode. Thereby, the microkernel architecture is excellently suited to implement a proper division of mechanism and policy. The kernel provides just the most basic mechanisms needed for an operating system, while the userspace modules implement the policy. This decoupling makes it easier to change the policy in userspace for altering requirements without touching the actual kernel [45].

What is part of this core functionality differs between miscellaneous sources, but all considered ones are in agreement that a simple mechanism for process scheduling is as well a core functionality as providing an Inter-Process Communication (IPC) mechanism[24], [39], [15]. In contrast, the sources disagree as to whether memory management and virtualisation, device drivers or synchronization facilities are a part of the actual kernel. The Mach microkernel, which formed the first generation of microkernels in 1985, named process and thread administration, an extensible and secure IPC mechanism, virtual memory management and scheduling as its core tasks, while everything else needed has to run in usermode [36]. Functional enhancements of the system do not require changes to the kernel itself, too. This concerns, depending on the exact relization, device drivers, memory management, system call handlers and even more system components[24], [39]. In academic microkernel approaches, all components in user mode run within an own userspace process as small, well-defined modules, while the communication is done through copious message passing via the actual kernel [45], [24]. Since the restrictions by the CPU's dual mode still apply for microkernel based operating systems is it not allowed to device drivers running in user mode to have direct physical access to I/O ports as a consequence. A device driver has to invoke the actual kernel to perform the needed action substitutional. But thus,

the kernel is able to check the action and whether the driver is authorized to executed them. Resulting, the microkernel design is more reliable and secure as such a division enables the kernel to intercept erroneous actions such as accidental memory writes to important regions[45]. Equally a crash in a userspace system component like a driver is not able to crash the entire kernel in such an approach. And as an additional advantage facilitate the microkernel architecture porting the operating system kernel to another target architecture as the most hardware dependencies are part of the small kernel[39], [24].

With all the named advantages microkernels offer, the question remains why microkernels are only spread in real-time, avionics or military but not for desktop operating systems. One reason is that all these advantages are bought at the high price of microkernel message costs. For the named application areas, especially the reliability that comes with the microkernel architecture is more desirable than the performance costs of the lot more context switches in comparison to monolithic architectures [45]. Since a lot of the operating system's functionality has been moved to the userspace, microkernel architectures need to perform noticable more context switches to invoke the actual kernel for privileged actions. The performance losses are not only caused by the large amount of context switches themselves, but also by the fact that modern CPUs, particularly the caches are not designed for them. Every context switch causes cache misses which trigger that the required data has to be loaded from the slower main memory and cached. The data of the previous context (e.g. the user mode context) will be displaced from the cache and the CPU is largely blocked in the meantime. By rapidly switching back to the previous context, as is usual for e.g. a short kernel invokation to perform an I/O operation on microkernel architectures, the cache is no longer suitable for the new context and has to be replaced [24].

First of all, the L4 kernel, a second generation microkernel was able to get close to the performance of a monolithic kernel as Linux it is[19]. This has been achieved by improving the Inter-Process Communication (IPC) mechanism, a fundamental component of microkernel architectures on which other communication mechanisms are based. Nevertheless are pure microkernels mainly used for systems with high reliability requirements but unusual for desktop application. Some industry examples are Integrity, QNX and seL4, a mathematically verified version of the L4 kernel[45].

2.1.3 Layered Architectures

Layered operating system architectures are usually organized in hierachical layers, but sometimes the choosen model is described as a series of concentric rings. Each layer or ring provides a group of functionality while a it is only allowed to use the functions of the one directly below. The cooperating between the layers or rings is regulated by clearly defined interfaces[5]. This is usually accompanied by the fact that the lower layers or inner rings are more privileged as the outer ones. However, there is no uniform and universally accepted approach for division in layers and their count according to this pattern[15], [45]. In fact, a meaningful division is not that easy. Functionalities may have to be divided artifically and the harmonious arrangement can have its

pitfalls caused by the access requirements this architecture is based on. Is the layered access model considered properly to get a clean architecture, it that can unfold its advantages. These are for example the interchangeability of the layers if they and their interfaces were properly designed or the resulting concept for debugging. As the layers are constructed on top of each other, it is possible to debug and verify each one for its own, starting at the lowest layer up to the top most one [39]. But also the costs for system calls are comparatively high, because they have to be passed though all layers while each one adds overhead to such a call [39].

In general, layered operating system architectures are related to monolitic ones, but it is conceivable to adopt the idea for microkernel approaches, e.g. is the MINIX userspace divided into layers. Examples for this architecture are OS/2 or newer Unix variants, while Multics is one for a concentric rings based model[15], [45].

2.1.4 Hybrid Architectures

Hybrid operating system architectures based on monolithic, microkernels and may be the layered ones are common approach to combine the advantages of these concepts. They try to pair the performance of the monolithic design with the modularity and reliability of microkernels[49], [39]. How both worlds interact is very different depending on the exact implementation. SILBERSCHATZ explains one of them in his book $Operating\ System\ Concepts$ [39] using Apple's $OS\ X$ (today named macOS) as an example. Depending on the exact implementation and the share of the architectures, most disadvantages of monolithic architectures still apply for the hybrid systems. Further examples for hybrid architectures are $Windows\ NT$ and BeOS[49].

2.1.5 The Linux Kernel's Monolithic Architecture

Linux is the perfect example for an extremly grown operating system. Starting as a pure hobby project to learn about a specific CPU and connect to the Unix computers at LINUS TORVALDS, its initial author's, university, it becomes strongly related to its archetype, Unix[10]. They share fundamental design goals, just like beeing capable of multiple processors and user at the same time, but Linux is not based on the origin Unix source code [45]. The overall architecture of the Linux kernel is, as already named, monolithic and also inspired by Unix[24], [10]. It is entirely running in kernel mode and all built-in layers have full access to the internal kernel Application Programming Interface (API) using common function calls like in C. A sophisticated concept of kernel modules which can be dynamically loaded to a running kernel makes a limited number of microkernel advantages available for Linux. Modules in Linux are only allowed to use a restricted (exported) set of functions to use, but once loaded to the running kernel, they become a part of the monolith running in kernel mode [24]. Linux is largely compatible to the POSIX standard which was initially created for Unix. Initally, it was because TORVALDS could not get a version of the standard, while today it is rather a conscious decision[10], [45]. Also the decision for the monolithic architecture is today consciously supported by the kernel community and justified with its performance and

efficiency over microkernels due to the *priviledge barrier* between user and kernel mode which has to be passed quite often in microkernel architecture[16], [24]. The Linux kernel itself is divided in five essential tasks which are also reflected in its source code. They are:

- Process Management,
- Memory Management,
- Filesystems,
- Device Management and
- Networking[24].

By structuring this tasks and further components into subsystems like drivers/, fs/ (filesystems), net/ or kernel/, the linux kernel remains comprehensible and in some ways modular. A closer look to the most of them in general but also their implementation in Linux is done in the following sections.

The Linux kernel is mainly written in C but some very hardware dependent part are in Assembly. Additionally, especially the Assembly parts were strongly dependent on the GNU Compiler Collection (GCC). Today, there are some efforts to reduce the share of Assembly for maintenance and readability since modern compilers do not generate less efficient code as hand-written Assembly is [17]. This also reduces the dependency to GCC and enables the use of alternative compilers, especially Clang[11], [9]. Nevertheless, the Linux kernel's principal lanugage is C and it only provides support for C drivers.

2.1.6 The Zircon Kernel's Microkernel Architecture

In contrast to the Linux kernel, Zircon is not a grown structure. Started in 2015, it was largely developed from scratch by Google for a so far undisclosed field of application[14]. Nevertheless, Zircon emerged from a branch of *Little Kernel* (LK) by TRAVIS GEISELBRECHT which is also a part of the Zircon Team at Google[30]. Despite its origin, Zircon is very different to Little Kernel. It targets powerful devices such as modern computers and phones and provides for this reason only 64-bit support, first class user-mode support and a capability-based security model. In contrast, Little Kernel is designed for embedded applications and amongst others used as bootloader for *Android* and as *Android Trusted Execution Environment (Trusty TEE)*[40]. It has 32-bit support, but none of the more sophisticated features Zircon has[30].

The mirokernel architecture is justified by having security, safety, reliability and modularity as major design goals for Zircon. According to TRAVIS GEISELBRECHT was the architecture a conscious tradeoff between the named goals and performance [14]. They try avoid costly context switches as much as possible, speed up the remaining ones and take advantage from SMP, but it is not the focus of Zircon. Alike, Zircon does not focus on performing I/O operatings or process management which are the key tasks POSIX was designed for [14]. As a result, Zircon does not claim to be or to become

POSIX compatible, they just support a very basic subset of the standard[21]. The Zircon kernel itself is splitted up into the actual microkernel running in kernel mode (kernel/) and services, drivers and core libraries running in user mode (system/)[41]. The kernel part provides the basic operating system mechanisms:

- Process Management,
- (virtual) Memory Management,
- Inter-Process Communication and
- Synchronization Mechanisms[41].

The part running in user mode contains core services for, amongst others, booting, device management and networking, device drivers respectively hardware related code and user libraries.

Zircon is for the most parts written in C++ and less in C. It provides native support for device drivers in both languages but due to the fact Zircon provides an Interface Definition Language (IDL) which defines a contract for in-process drivers, other languages are conceivable as well. In fact, support for Rust drivers is currently beeing worked on [14]. Unlike Linux, Zircon provided support for both, the GCC and the Clang compiler, from the beginning caused by the sophisticated tools aroung Clang and LLVM.

2.2 System Calls

System calls were already marginally mentioned in this work as the mechanism to switch the program execution between user and kernel mode, because applications running in user mode have only restricted rights. Thus, this special calls are needed for the interaction with basic hardware devices like the CPU, the memory, peripherals or filesystems and for invoke the actual operating system's kernel for management operations like process management[24]. System calls are to a high degree hardware dependent and differ between various operating system implementations.

A system call has its origin in an application running in user mode. If the application has to invoke the operating system kernel, e.g. to perform an action on memory in substition, it has to use one for switching the operating mode[15], [45]. As switching the CPU's execution mode also means a new context, a system call to the kernel differs from a common procedure call. In user mode, the so-called entry code stores the system call's parameters in a defined way. One is to store the parameters and the call's number in defined registers (see 2.3), another one is to store them on stack, according the C/C++ calling in reverse order[39], [15]. The exact one depends on the actual CPU architecture. The following instruction triggers a specical software interrupt containing the order to switch the context. It is also named trap instruction[15], [45]. To be exact, it is the interrupt vector number of the trap instruction which is responsible for the switch. They are 080 on Linux as pictured in 2.3 and 02e on Windows systems[15]. But right before switching it is needed to save the Program Status Word (PSW),

which contains the actual processors state includes the mode bit, to the stack. The same number is used in kernel mode as an index within the interrupt vector table (or interrupt discriptor table, IDT) which contains the start address of the system service dispatcher routine (compare to 2.3). This tables content, the system serice dispatcher routine, is loaded as next instruction to the new PSW[5]. Jumping to this routine, the system call's parameters and its number are restored to examine the actual call and invoke the matching service routine from the system service dispatching table which finally fulfils the requested action as simplified pictured in 2.3[15]. Conclusively, the control flow jumped back to the system service dispatcher which hands the control back to user space inclunding switching back to user mode in the common way to return[15]. The previous PSW is restored from stack containing the bit for CPU's user mode execution. The user application has to clean up the stack like for each procedure call at the very end[45].

Figure 2.3 shows a simplified version of the system call implementation on x86 for Linux kernel before 2.5[3]. More modern versions use the special instructions SYSENTER and SYSEXIT (Intel) or SYSCALL and SYSRET (AMD) instead of the slower trap interrupts[3].




Figure 2.3: System Call Implementation[24]

POSIX

The basic idea behind the Portable Operating System Interface for UniX (POSIX) standard is to define a stable interface between the user-space and the operating system kernel to archieve portability for applications on systems meeting this standard. But even if an operating system comply the them, it may differ in the typ and number of available system calls. POSIX is only an API definition but not one for system

calls. An operating system may implement the POSIX standard functions within a library which often involve system calls, but it has not to do so[24], [15]. System calls are rarely used directly by user applications without an abstraction layer such as libraries. An example is the *libc* on Unix-like systems[24], [45]. Equally, a system is not constrained to a single API and may implement different ones using its existing set of system calls[15].

POSIX is a very common standard which is for example implemented in UNIX, macOS, MACH and partly in Linux[45], [15]. Another example for an API is Win32 used by Windows to abstract their system calls, but as a result, applications targeting the Windows Win32 API are not portable to systems implementing the POSIX standard.

2.2.1 System Calls in Linux

In fact, the way system calls are working in Linux was already described as part of the general section. The exact mechanism, the calling convention but also the number of system calls is highly depending on the CPU's architecture. While a 32-bit Linux kernel in version 4.8 for the x86 architecture offered 379 calls, the 64-bit version for x86_64 offered only 328[24]. The man-pages project documents gives an overview (man 2 syscall) about architectural differences and the calling conventions. How far Linux is acutally compatible to the POSIX standard is not only related to the kernel and the number of system calls itself, but for the most part to its abstraction layer, the used POSIX/C standard library. One of the most spread ones, the glibc (GNU C Library) aims to follow POSIX.12008 amoungst other standards² while the musl library does not implement it in complete³.

2.2.2 System Calls in Zircon

In Zircon, system calls are bounded to the concept of *handles*, a construct which allows applications running in user mode to reference an object in kernel mode [42]. Interactions between user applications and kernel objects are still done using system calls but the most of them are using a handle which describes the kernel object to work on [29]. Handles are checked by the kernel each time a system call is triggered. For additional security, the kernel checks wether

- a handle has the correct type for the system call,
- a kernel handles parameters refers to one existing within the calling process's handle table and
- a handle has the necessary rights for the triggered action[29].

In contrast to Linux, Zircon provides just one libary for system calls and the standard C implementation, the *libzircon.so*. It is a virtual Dynamic Shared Object (vDSO) directly provided by the kernel and not stored as a physical Executable and Linking

²https://www.gnu.org/software/libc/

³https://repo.or.cz/w/musl-tools.git/blob_plain/HEAD:/tab_posix.html

Format (ELF) file on disk. For the reason that vDSOs are accessable from both, kernel and user mode, without switching the context, they are a perfect concept to implement system calls in a very performant way[8]. Thus, the Zircon vDSO is the only way to perform system calls[28], which is a very elegant solution to cope with performance issues in a microkernel architecture.

The system calls are defined by using a abstract definition syntax and the matching tool abigen which generates header files and code for the libzircon and the kernels system call implementation[29]. Also in contrast to Linux does Zircon respectively Fuchsia not aim for POSIX compatibility. It implements only a very limited subset of POSIX consisting of basix I/O operations and pthreads. Zircon does not support Unix-like signals, symbolic links and much more[21]. The libzircon.so does not support directly I/O operations. They are performed by the fdio.so library which overwrites weak symbols of the libzircon[21]. All available system calls in Zircon from the version this thesis is working on are documented in https://github.com/Allegra42/zircon/tree/i2c-grove-lcd/docs/syscalls.

2.3 Processes and Threads

Modern operating systems are characterized by their ability to perform various tasks at the same time. So far, this fact has simply been accepted within this work, but it was not questioned what is special about it and how this multitasking is achieved by an operating system. In general, parallelisation of tasks can take place on different levels, e.g. as hardware or software paralellism. While the physical resources for the first case are actually available to execute the tasks really simultaneously, it only seems to be so for software parallelism[15]. Hardware parallelism is realized by independent, may specialized execution units such as multiple processing cores or controllers which are able to perform particular parallel to the main CPU. This could be USB, network or graphics controller, for example [15]. In order to create the impression of parallelism on a single CPU and to use their available computing power as best as possible, an abstraction to provide pseudo concurrency for the execution of several tasks is required. According to Tanenbaum, this concept called *process model*, is the most central one of operating systems [45]. The term process is often defined as a program in execution [1]. The process model is complemented by the thread model which provides a simplified version for paralellism within a process or an application [15]. The following sections take a closer look at these concepts and answer the remaining questions, in particular about the process and thread model, synchronization mechanisms, inter process communication and their implementation in Linux and Zircon.

2.3.1 Processes

The term *process* describes an instance of a program in execution, including all its required resources to enable a model for the pseudoparallel execution of multiple programs based thereon[39], [45]. Each program in execution is modeled as a seperate process which is assigned to a virtual private CPU including CPU registers, above all

the program counter (PC) and a virtual private address space[45]. [15]. Especially by using virtual private memory, processes are not only modeled individually, but are also isolated from each other in reality in order to prevent errors or deliberate attacks between programs[5]. But since in reality more processes, respectively programs, have to be executed than CPUs exists, a mechanism is needed to switch between processes and allow the execution of all them. This mechanism behind, the multiprogramming model, and the policies called process scheduling will be considered hereafter.

However, for a change between the execution of programs to succeed, a process must contain information about its state at the moment it is interrupted to run another one. Which information need to be stored and the way it is done is slightly depending on an effective system's design and its implementation. In general, these information are stored in a structure called *process control block* in literature [45]. Depending on the implementation, it contains for example

- an process id,
- the process's state,
- the CPU's register contents, especially the program counter (PC), the stack pointer (SP) and the processor status word (PSW),
- the process's address space including the program code, its stack and heap and data segments,
- information about resources allocated by the process like open files, or I/O devices,
- CPU scheduling and accounting information like a priority, the maximum and actual computing time for this process,
- the parent process and
- the process's rights[45], [15], [1], [39].

Process Lifecycle

The state in the list above refers to a process's lifecycle. It is quite easy and in most cases described as a state chart like pictured in figure 2.4. Once a process was created, it is managed by the operating system and changes its state to ready. The process is ready to run, but has to wait until the system allocates a CPU to it. Is that the case, the process changes its state to running and performs its calculations. If a process is interrupted (preempted) by the operating system without having fulfilled its task completely, there can be two reasons for this which result in different subsequent states. Was the process interrupted just to run another one, the process's state changes back to ready. It only lacks on CPU time to run the process again. If the reason was instead that resources like the process is waiting for an external event or required I/O devices are used by another process, so it changes its state to waiting or blocked. Only

when the blocking resource needed by the process is available again, the operating system changes the status of the process to *ready* again. The process is prepared to get reassigned to a CPU. A running process finishing its task during its computing time has reached the end of its life, its state changes to *terminated*. The operating system destroys the process and frees related resources[39], [26].




Figure 3.2 Diagram of process state.

Figure 2.4: Lifecycle of a process[39]

The model described applies to each individual process. For the coordination of the entirety of processes, the schedule, an operating system kernel's component is responsible. It is a good example for the seperation of mechanism and policy. The mechanism behind is based on the *multiprogramming* model as the switching of the CPU between programs is called. It not only allows the impression of parallelism on a single processing core, but also increases its utilization, as many processes spend a lot time waiting for external events such as keyboard inputs[45].

Principally, the mechanism behind scheduling does not differ fundamentally from the treatment of an ordinary interrupt. First, the programm counter (PC) is saved prior to the new PC is loaded from the interrupt vector and the CPU's registers are saved. After a new stack was setup, the actual interrupt service runs before the scheduling policy decides which process is to run next and the selected one is started [45].

Process Creation

There are several reasons why a new process should be started and scheduled at all. The most basic one is the systems start-up. To initialise an operating system are numerous processes created to execute parts of the system itself. The user perceives very few of them directly, since the most of them are background processes performing specific tasks like accepting incoming mails. Often, long running processes without user interaction are referred as deamon processes[15], [45]. They are mostly generated from the init process, the first one running and bringing up the system. Foreground processes, the ones an user interacts with, are more often started on behalf of the user. Besides, a process can also be started by a system service call from an existing process.

The last option, that a process is started to execute a batch job is rare today apart from scientific high performance computers [45], [15].

Also for the way how a new process can be started there are several options. Using process chaining, a running process starts an independent new one, a new Process Controll Block (PCB), and destroys itself[1]. An example is the Unix implementation of exec()[15], [45]. By forking a process, a second one that is, at least in the beginning, a copy of the original one. Both remains exiting and share the same environment such as program code, address space and resources[45]. As a result, both processes have access to the exactly same resources like opened files or I/O devices[1]. The Unix implementation of fork() is an example for this way of process creation. Process forking and chaining are usually used combined in Unix-like systems to create a new, independent process which is running in parallel to the first one[45]. In contrast, Windows offers a third way the process creation which combines them in a single instruction to start a second, independent process (CreateProcess())[15].

Are the newly created process and its parent share the same program code, the new one can simply inherit all needed data from its parent like it is done by process forking[1]. Since each process has its own virtual address space if not shared through inheritance, so the data cannot be copied there without further ado. This is not only necessary for the multiprogramming model, but also a security mechanism that encapsulates and protects applications in execution against each other, called process isolation. Is is the case, e.g. for the once created via process creation, an operating system needs a mechanism to pass data to the created process. As a solution, a mechanism for the communication between processes with which the parent process communicated the new data to the child one via a buffer is just as conceivable as the use of inital parameters which are transmitted during the process creation, e.g. via a system call[15]. The first option is used by the popen() call of Unix-like systems while the mechanism behind the IPC takes a major role in modern operating systems and therefore is treated in a seperate section. The second one is more often used for threads which are the topic of the following section.

Process Termination

Reaching the end of its lifecycle (see figure 2.4), a process terminates itself regulary and voluntary (normal exit)[45]. In addition, a process can terminate itself prematurely for various scenarious or be terminated by the operating system or other processes. For example, a process may detect an internal error and voluntary terminates itself ahead of time or the operating system detects such an error and terminates the process involuntary to avoid major damage[45]. Besides, a process may gets involuntary terminated or killed by another process. Killing another process is in common a privileged task which require an authorization or extended rights[45].

2.3.2 Threads

The current process concept, as previously introduced, provides only a single thread of execution. However, this an issue as soon as a resource needs to be edited in parallel. If

an user edits a file for example, the process has to wait for the user's input repeatedly. It is nearly impossible to check this input for errors at the same time, since a second process is not allowed to access resources allocated by another process without an explicit action of programmers (like explicit Inter-Process Communication)[45], [5].

The thread model should solve this issue. Its basic idea is to equip a process with several execution threads that work on the same resources running in quasi-parallel[45]. This means processes only group the resources together while threads represent the actual execution units on the CPU[45]. A program is still abstracted as a process while (parallel) sequences within the program correspond to threads. As a result, threads can be considered as slimmed down processes sharing the same address space and physical resources. Each thread has its own Program Counters (PCs), register set, stack and state, but the address space, global variables, open files and accounting information are shared[45]. A thread's lifecycle is equivalent to process's ones, but in contrast to them are threads not isolated and protected against each other[15]. As they share the same address space, one thread can read, write or even destroy another thread's private stack[45]. Another issue are competing threads that try to write the same global data. They cause a race condition which possibly result in inconsistent or wrong data[5].

Nevertheless, the advantages of using threads (multithreaded programming) predominate. The most important one is resource sharing. The fact multiple threads using the same resources by default, e.g. files, in pseudoparallel are the biggest advantage but at the same time the biggest problem of this concept. Threads enable responsive, interactive applications and increase the performance especially on multiprocessor architectures they can run truely parallel[39]. Another reason is an economic one. While allocating an address space and physical resources to create a process is an expensive operation, creating a thread is not as they inherit exactly these components from their corresponding process[39], [26]. Threads only need to setup their own PC, registers, stack and a state within a process. That's why they are also known as Light-Weight Process (LWP)[26].

How light-weight they actually are depends a lot to their implementation in an operating system. Conceivable options are thread implementions in userspace or kernel space, but also hybrid ones. Implementing them as user library requires an own mechanism to schedule threads within a process which is often realized as a kind of runtime environment including a Thread Controll Block (TCB) (according to PCB) for each single process[26], [45]. There is no need to invoke the operating system to switch a thread, but as a result all threads within a process block become blocked if a single one waits for a resource [45], [5]. The operating system's schedule just do not know about the runtime environment and possible other runnable threads within a process. The implementation in kernel space is not that light-weight, but multicore architectures benefits more from this variant. If the operating system's kernel has the control over threads, these are managed just like processes. Instead of one TCB within each process, the kernel collects the TCBs for all threads in the entire system in a thread table according to the process table [45], [26]. But this also allows the kernel to recognize a blocked thread and schedule another one of the same process instead of blocking the whole process[45].

2.3.3 Processes and Threads in Linux

As in the general model, a process in Linux corresponds to a program in execution. Initally, a process contains exactly one thread of execution but further ones can be created as soon as the process has started [45]. Processes are organized in a treelike structure with the so-called init process on its top. Starting from init, each new process to be created is split off from its parent using the fork() system call. Forking a process, the newly created child process inherits the whole environment of its parent including environmental variables, opened files and network connections. Furthermore, it gets a copy of its parents address space including the data and code sections. As both processes share the same data and resources at this time, synchronization is needed if both try to access the same one [26]. This issue is considered in the following section 2.4.1. The distinction of parent and child is done via their Process Identifier (PID). The fork call returns 0 to the child and a non-null PID to its parent. Based on this, the execution paths can be splitted up[45], [26]. Even if parent and child differ only by the PID directly after the fork, changes in the parent are not visible to the child and vice versa. To take advantage of this fact to actually use the new created process independently of the parent, in Unix-like systems the fork call is in most cases directly followed by the call exec(), which replaces the the complete process environment with the one from another, new program. As copying the process data is quite costly and needless if an exec follows directly, modern Linux systems use a copy-on-write strategy for process forking. Childs get own page tables pointing to the parent ones. The child still can read the parent's environment data without a copy operation needed. Only when the child tries a write access on this data, a protection fault is thrown and the page to modify is copied to the child process [45]. Such a fork is known as vfork()and used especially in situations a exec() follows directly to avoid the expensive and needless copy of the parent process's environment[26].

Within the Linux kernel, the difference between processes and threads (or heavy-weight and light-weight processes) is not as important as described in the general section about processes. It is rather spoken of *tasks*. The reason for this is that the Linux kernel offers a possibility for a fine-granular process respectively thread creation via the *clone()* call on kernel level. In addition, Linux respects POSIX threads[24]. But as the clone call is an unique feature of Linux and not generally available on other Unix-like systems are application using the clone call directly not portable[45].

Nevertheless, *clone()* is a very interesting concept in Linux. In each case, a process or thread created with clone gets an empty private stack and executes directly a new program which is given as an argument to the call. The decisions whether a process or a thread should be created, which resources should be shared or copied and which process is actual the parent are based on the following flags:

- if CLONE_VM is set, a new thread is created, if not, the call results in a new process.
- if CLONE_FS is set, the newly created thread or process shares *umask*, *root* and *working directories* with its parent. They are not shared at all if the flag is not set.

- if CLONE_FILES is set, the parent shares file descriptors with its child. If not, they are copied to the child.
- if CLONE_PARENT is set, the child's parent is the same as the calling process ones. If the flag is not set, the calling process becomes the parent [45].

The flags listed show only a partial amount of the possibilities clone() offers. A full list the glibc wrapper to the corresponding systemcall is available as a man-page using man 2 clone. Both, processes (tasks) and threads based on the clone call are kernel constructs. The POSIX thread implementation on Linux internally also uses the clone call with the special flag CLONE_THREAD.

In contrast to the process lifecycle presented in the generic section, Linux tasks have one extra state called *zombie* which is entered on process termination until the parent process is informed about [26].

2.3.4 Processes and Threads in Zircon

Similar to Linux, runnable entities of the Zircon kernel are called *tasks* objects. This term includes the kernel objects *jobs*, *processes* and *threads*. As the whole Zircon kernel is object-based, the user interacts with kernel objects like the ones mentioned above via handles. The Zircon documentation describes *handles* as "kernel constructs that allows user-mode programs to reference a kernel object" [34], containing the reference to this object, the corresponding rights and the user-space process bounded to. Thus, a handle can reference each object type listed in the *Zircon Kernel objects* reference [23], including kernel objects for drivers like *interrupts*, *resource* objects and *Log* objects. The Zircon systemcall zx_status_t zx_task_kill(zx_handle_t handle) is such an interaction between an user application and the kernel. It refers to a *task* object handle and thus to all objects for which *task* is a generic term[18].

Jobs as an organizational unit are Zircon-specific and not known from the general or the Linux-specific section on processes and threads. A job manages a group of processes but possibly other (child) jobs, too. According to Linux, jobs built a tree structure as every process must belong to a single job but jobs can be nested. Except the root job, which corresponds to the init process on Linux, each one has only one parent. A Job object consist of a reference to a single parent job, a number of child jobs and a set of member processes. In future⁴, they will also contain a set of policies[32]. Jobs are used to track the privileges needed to perform kernel related operations like systemcalls but also to track and limit the consumption of basic computing resources such as memory, CPU time or I/O devices[32]. The idea behind this concept is managing applications composed from more than one process as a single entity, both from a resource and permission view as well as from lifetime control[34].

A Zircon *process* itself is an instance of a program as defined in the general section about processes 2.3. It consists of the program code as a set of instructions to be

⁴Unless otherwise noted, the status of the Zircon documentation cited in this thesis corresponds to the forked and frozen source code repository on which basis the driver development takes place. See https://github.com/Allegra42/zircon/blob/i2c-grove-lcd/docs/.

executed by one or more threads and a collection of resources. Threads are just as much a part of a process' resources as handles and Virtual Memory Address Regions (VMARs) are [34]. Strictly speaking, it is not necessary to mention VMARs as an own point. They are kernel objects itself. But as the documentation mentions them explicitly, they should also receive special attention in this place. A VMAR represents a contiguous part of virtual memory address space used by the kernel as well as by the user-space. Each process starts an own VMAR to built up its address space. VMARs have a hierachical permission model, so a process with a read only address space cannot create a readable and writeable one, and are randomized per default [13].

The lifetime of Zircon processes differs from the general but also from the Linux model. In Zircon, a new process is created via zx_process_create() but the execution starts not before zx_process_start() is called. Once a process started and exits its last thread, it is impossible to add a new thread. Processes which are composed to a job are threaten as a single entity from a lifetime control's point of view. The lifetime of Zircon processes (or jobs) ends if

- the last thread within the process or job exits or is terminated,
- the process or job itself calls zx_process_exit(),
- the parent job terminates the process or
- the parent job is destroyed[34].

Just like known from the general section are Zircon threads the actual runnable computation entity living within a process. They are created within the process context via zx_thread_create() but as it is done with Zircon processes, the actual execution is not started until zx_thread_start() or zx_process_start() is called. The main() function or entrypoint of an application should be the first one started via zx_process_start(). But returning from such an entrypoint does not terminate a thread's execution. This must be done manually by voluntary calling

- zx_thread_exit(),
- zx_vmar_unmap_handle_close_thread_exit(),
- zx_futex_wake_handle_close_thread_exit()

on the thread itself[35]. Even if the last handle to a thread is closed, the thread is not terminated automatically. Instead the thread must be killed explicitly after the handle was restored via calling zx_object_get_child() on the parent. On the other hand, a thread can be terminated involuntary

- if the parent process is terminated,
- if someone calls zx_task_kill() on the thread's handle and
- if an exception was generated for which is no handler or the handler terminated the thread[35].

In contrast to Linux threads and some library thread implementations, Zircon threads are always *detachted* from each other. An operation like <code>join()</code> which waits for an undetached thread to complete and allows a clean termination is not needed in Zircon itself. Libraries and runtime environments on top of Zircon may require such an operation to reach e.g. POSIX compatibility[35].

2.4 Synchronization and Inter Process Communication

The term Inter-Process Communication (IPC) is not only used for the pure communication between different processes but also for the synchronization between processes, threads and data shared between them. In this context mentioned already the previous section 2.3.2 that the ability of threads to access shared data not only has advantages. As they share storage, e.g. main memory, two threads can read and write the same value. But what happens if both of them try to access the same, shared value? Two threads try to read and modify a shared value are given for example. Both read the value and calculate based on the read a new one to store. There is no problem as long as they just read the same value, but it occurs on updating the value. May the first thread is scheduled first and updates the value, directly following the second one is scheduled and updates the value based on the value read before the first thread was executed. In this case, the update of the first thread is lost. The data becomes inconsitent. Such a situation is called *lost update problem*[15]. Unless the scheduling of the threads is predictable in each situation, it remains impossible to predict the exact outcome. Therefore, one speaks of a race condition [45]. The section 2.4.1 deals with corresponding problems, especially for threads, and indicates ways to deal with them. Since it is not sufficient to allow only the exchange of data respectively communication between threads of a single process, section 2.4.2 shows mechanisms that overcome the process isolation and enable the communication between multiple ones.

2.4.1 Synchronization

In the context of this section, it should be assumed that *threads* are implemented as a part of the operating system's kernel rather than based on a runtime system. According the definition, the term *thread* refers in this section both, execution threads within a single process and the ones within independent processes. A competitive situation can occur for both variants. The threads of one process rather rivale regarding a shared variable while the threads of different processes rather compete for resources such as a printer.

Race conditions are a topic each time several processes or threads work on the same data in any way. This also applies to an operating system's kernel, except for non-preemtive kernels which can guarantee that only one thread is active at a time[39]. In contrast to preemptive kernels, non-preemptive ones do not allow a thread running in kernel mode to be interrupted. The thread runs until it exits kernel mode, blocks or

yields the control of the CPU voluntary[39]. Only in such a case can be guaranteed that a kernel and its data structures are free of race conditions. However, preemptive kernels are more common because they are more responsive and better suited for real-time tasks due to their interruptibility[39]. Furthermore, with today's multicore systems is it rather unlikely to fulfil the requirement of only one active thread in kernel space.

For this reason, a mechanism to prevent race conditions on both, user and kernelspace, is needed. The basic idea behind is to exclude the chance that a thread trying to change a shared resource is interrupted by another one trying to work on the same resource [45]. But only certain areas in the program code are critical, the ones a shared resource is processed. They are called *critical regions* or *critical section* [45]. Other regions do not harm if they are interrupted. If only one thread at a time is allowed in critical sections and another one is not allowed to enter the region until the competing access is completed, this is called *mutual exclusion* [45], [15].

The easiest way to achieve mutual exclusion is to completely disable the system's interrupts immediately after entering a critical region and reenable them just before leaving it. In the meantime, all incoming interrupts are collected and processed as soon as they become reenabled[1]. However, this method is not suitable for modern multicore systems since the interrupts can only be locked for the current CPU core. The competing thread can still modify the resource if executed on a different core. This solution is not ideal for single core systems, too, because even the clock interrupt is disabled and with this the process scheduling. Does the currently running thread not reenable the interrupts, the whole system is blocked[45].

While there are some approaches to pure software solutions such as the algorithms of PETERSON or DEKKER (see [45] or [39] for further information) are hardware enabled solutions common today [45]. Modern multicore CPUs usually offer an instruction which is referred as Test and Set Lock (TSL) or Test and Set (TAS) in literature. It is an atomar, not interruptible operation, usually used to modify a shared variable which controlls the access to a shared memory region [45]. The atomicity of a TSL instruction is in common achieved by locking the memory bus to prevent other CPUs from accessing the memory until the operation is done. As a big advantage of this solution, the CPU cores are not obstructed. Common calculations are not impeded but memory accesses are prevented [45]. A variant is the Exchange (XCHG) instruction which exchanges the content of two memory locations in one atomic operation [39].

All mechanisms mentioned so far have one problem: they require busy waiting. The thread waiting is still active and waists CPU time. For short waits, this is perfectly fine. Switching to another thread and back would be more expensive in such a situation [15]. Thus there are locking mechanisms that implement busy waiting very efficiently, called spinlocks [45]. But longer active waits are very inefficient. In this case, it is better to use blocking waits and bring another thread in execution until the reason for the blocking is removed, e.g. the desired resource is freed again.

Semaphores and Mutexes

DIJKSTRA suggested in 1965 a possibly blocking lock mechanism called *semaphores* based on a CPU's TSL instuction and easier to use for application developers. A

semaphore is a new integer typ with two related operations called P and V in the original paper or down and up in some literature and implementations[15]. The semaphore is initially initialized with a value greater 0, the exact one depends on a system's implementation or can be defined by a programmer. If the P or down operation is executed on a semaphore, it is checked whether the value is greater than 0, decrements the counter if it is the case and continues. If not, the thread is put to sleep. The operation remains unfinished until a V or up operation was executed and incremented the semaphores value. One of the possibly multiple threads sleeping on a semaphore is randomly or by a certain rule choosen by the operating system and gets the clearance to complete the P or down operation[45]. For a semaphore, the fact updates on its value must be performed in an atomic operation is essential[39]. Neighter the decrementing of the value performed in the P operation nor the incrementing in V may be interrupted.

Semaphores are a generic approach to control access to a *critical section* for a number of threads, but the often required mutual exclusion is only given if the semaphore is initialized with the value 1. These particular case of a binary semaphore is also referred as mutex. A mutex guarantees mutual exclusion for a critical section protected with its related operations as lock (P, down) and unlock (V, up)[45]. Except for the initial value and the operation's names, mutexes do not differ from semaphores. Just like semaphores, they can be implemented using the TSL or XCHG instruction.

But if semaphores are actually blocking depends on the implementation. As mentioned earlier is a blocking mechanism not always advantageous, e.g. for very short waits or multicore systems with real parallelism. In this cases, its is potentially more efficient to use busy waiting with spinlocks[15].

Futexes

Another variant of semaphores is the fast user-space mutex (futex). It targets the issue that neighter busy waiting nor block and reschedule another thread is very efficient on modern multicore CPUs. On a very parallel system, there are many contentions for resources which would require frequent switching of the active threads, but scheduling another thread respectively process requires as well expensive switches to the kernel[45]. futexs are not a pure userspace construct even if the name suggests. They still need a wait queue in kernel to manage the contenting threads waiting on a lock, schedule another thread (futexes are blocking by design) and putting a thread into the queue requires a system call as well. An user library tests a lock variable using a TSL instruction. If the lock is already held by another thread, the library has to put the thread to the queue. But if there is no contention is there also no need to involve the kernel[45]. The less actual competitive situations occur, the more efficient are futexes compared to common mutexes. Mutexes are for example used as part of the Linux kernel. In this context, INGO MOLNAR published an article⁵ as part of the Linux kernel documentation covering the implementation of robust futexes and and its

 $^{^5} https://git.kernel.org/pub/scm/linux/kernel/git/torvalds/linux.git/tree/Documentation/robust-futexes.txt$

impact on the system performance.

Barriers

So far, the synchronization of resource accesses has been discussed. Sometimes, this is not an issue but coordinate and synchronize the sequence flow of two or more threads. If threads within an application are divided into self-contained phases, it must be ensured that the next phase is not started until the current one has been completed by all threads involved [45]. The synchronization points where the threads have to wait for each other to enter the next phase are called *barriers*. An example for such a situation could be cooking. The stoven must not be switched on until all ingredients have been purchased. In contrast to the general implementation of barriers, a common real world stove does not block itself should this not be the case. In most instances, barriers are alternating implemented on the basis of blocking semaphores [15].

2.4.2 Inter Process Communication

While the previous section 2.4.1 focuses on threads, the actual one explicitly deals with the communication between different processes and their synchronization. As IPC is a central element in operating systems, especially in microkernel architectures, which significantly influences the system's behaviour and performance are design aspects and their effects an essential component to be considered.

Memory Based Communication

Since the communication of threads of one process via its shared address space is already known, it is obvious to think about a comparable technique between processes as well. But in contrast to threads within a process, the concept of process isolation must be considered here. As a security feature, it is not possible for processes to share their address space. The basic idea to implement a corresponding idea nevertheless involves the idea of using an external shared memory region which is requested from the operating system. It allocated the memory and show it in the address space of both processes[5]. The shared memory region is the responsibility of the processes, must be managed and secured against incorrect access by themselves[5], [15]. As known from thread communication, the advantages from this solution are the performance and transparency of raw memory access, but it also needs additional (manual) synchronization to obtain and maintain consistent data[15]. Nevertheless breaks this solution the isolation between processes. A variant of this idea is using files or similar resources as a communication medium. In this case, the process isolation remains, but manual synchronization, as described in the previous section, is still necessary[5].

Message based communication

Message based communication methods are more wide-spread. In contrast to the memory based ones, the synchronization usually does not have to be done manually. The

message exchange and with it the synchronization are provides by the operating system respectively its kernel via two primitives: send() and receive()[45].

Basically, there are three types of messages:

- A *Message* is characterized by a delimited amount of data within a single communication.
- Streams can theoretically transport an unlimited amount of data. In practice, there is a limitation not visible for the sender and the receiver.
- Packets organizes the data to transport in standardized formats, the communication protocols. They allow fragmentated transfer of a large quantify of data which is defragmentated on receiver side. The system implementation hides this fact, so the packets itself are not visible for an application[15].

Regardless of the type of message, there are two basic operations available for message-based communication: send() and receive(). These operations are commonly supported by the operating system and enable not only the system-wide but also the cross-system exchange of messages and data[15]. Especially the opportunity of cross-system communication offers a significant advantage over memory-based communication, as this is the foundation for network communication. But also the synchronization between the involved processes is simplified. The concept of messages avoids race conditions and maked the manual use of semaphores for application developers obsolete, as the operating system realizes the transmission of the messages and their synchronization. However, this concept is not as efficient as memory-based IPC concepts in terms of resources consumption and performance[15].

Synchronous and Asynchronous Communication One of the most basic design decisions within message-based communication is whether to send or receive messages synchronously or asynchronously. When transmitting messages synchronously, both sender and receiver must be ready for the exchange at the same time[15]. Is this not the case for one instance of them, e.g. the receiver, the other one (the sender) must block until the first one, the receiver, becomes ready. An additional, manual synchronization is not necessary. Even if the literature does not describe a general way to transfer messages between processes, race conditions cannot occur as long as a date is only sent from a writing process to the address space of an initially reading process and can only be modified there[5], [15]. However, within the individual processes, the synchronization corresponds to the one known from threads (see 2.4.1). But the close coupling of the processes within the synchronous communication leads to the fact that the program flow of both is no longer possible independently of each other. Accordingly, the parallelism for processes in such a relationship is also limited[5].

The asynchronous approach tries to decouple this by inserting a buffer between which is also known as mailbox or message queue. So sending is possible even if the receiver is not available at one moment, as long as the buffer is not completely filled. The receiver can read equally if the sender is not ready, but the buffer still contains messages. Even different processing speeds between the processes involved can also be

compensated in this way[15], [5]. Only if the buffer is completely filled, the sender has to be blocked and vice versa the receiver if the buffer is emptied. But an operation only blocks when running in a blocking operation mode. In a non blocking operation mode, a call returns immediately in such a situation but reports a full respectively empty buffer which has to be handled on application level[15]. Asynchronous communication allows a independent program flow and simplifies paralellism thereby. Nevertheless, an additional buffer with limited size is needed. The exact one depends on the implementation. If this buffer is filled and the receiver is blocked, the situation is the same as before with synchronous communication. But the main problem with this approach is that it is not possible to predict how long a message transfer takes and when a response can be expected[15]. The issue is to decide whether a message is lost, the communication only takes a long time or the receiving process has crashed[45].

Connection-Oriented and Connectionless Communication Especially when the reliability of data transmission has a great significance, a connection-oriented approach for message-based IPC is choosen. This allows to guarantee the message sequence, monitor the transmission time of them and to intervene if necessary[15]. Until a (logical) connection or channel between the communication partners has been established, the initial message receiver must be unambiguously known. As soons as this is the case, the identification is not longer of relevance. The established channel provides a reliable end-to-end transmission which may have the following properties:

- An *unidirectional* connection allows message transfers only in one direction at a time.
 - If the roles of sender and receiver never change, one says the transmission is simplex.
 - If the participants alternate act as sender or receiver, the transmission is also called *half duplex*.
- An bidirectional connection allows message transfers in both directions. Both participants can act as sender and receiver at the same time. The transmission is full duplex[5], [15].

If a connection is no longer needed, it must be disconnected and destroyed. The construction and dismantling of a connection means an additional and noticable overhead especially for small amount of data to transmit. Is only worthwhile if the reliable transmission between designated instances is more significant as the connection costs[15]. One example for connection-oriented communication is a telephone call.

But there are also good reasons for *connectionless* communication. For example if the overhead of the connection setup is too costly for little data to be transferred or rather few data is send to a large amount of receivers. A real world example for *connectionless* communication is radio. The order of messages cannot be guaranteed for this connection type and also the loss of them is possible, but this has no further impact on the application[15], [5]. Nevertheless, the recipient must be addressed anew in every single message.

Receiver Addressing Message receivers respectively their message queues are commonly addressed by a symbolic name which is managed in a system-wide or cross-system directory. When addressing them, one speaks depending on the number of receivers and the liability of the transmission of:

- a *unicast*, if there is a 1:1 relationship between sender and a certain receiver addressed.
- a *multicast*, if there is a 1:m relationship between sender and a defined group of receivers addressed.
- a *anycast*, if there is a 1:1..n relationship between sender and group of receivers. At least on recipient from the group must receive the message.
- a *broadcast*, if there is a 1:n relationship between the sender and all dectectable receivers. Whether the message actually arrives does not matter[15].

Priority In literature, asynchronous message-based IPC mechanisms are usually modeled without prioriizing messages. A buffer, message queue or mailbox that works according the First In First Out (FIFO) principle is suitable for this purpose. In order to enable a priorized message exchange, it is, iter alia, conceivable to use separate buffers or queues for each priority[15], [45].

2.4.3 Synchronization and IPC in Linux

Basic Synchronization

Modern Linux based operating systems provide a wide range of basic thread synchronization mechanism from a user's point of view. Examples are POSIX realtime semaphores, POSIX mutex and System-V semaphores[15]. The underlying implementation in Linux versions starting from 2.6 is based the concept of futexes to provide an efficient locking mechanism[45]. While in userspace the grown structure of Linux, its openess, but also standards like POSIX allows to find nearly every variant of basic synchronization mechanisms, the kernel itself is much more limited.

Within the actual Linux kernel, only spinlocks and mutexes are available besides atomic data operations like atomic_set(), atomic_inc(), atomic_dec() and others[1]. As mentioned in the general section 2.4.1, a spinlock uses busy waiting while the kernel's implementation of mutexes is a blocking one. Both are binary semaphore versions that only differ in terms of waiting behaviour[38]. Linux versions compiled for single processing core systems and without preemption support do not provide any locking mechanism at all. It is not needed in this case. Preemptible single core systems provide spinlocks but they only disable preemption during a critical region[38].

Signals

Signals are a special concept of UNIX and Unix-like operating systems, located somewhere between process synchronization and IPC. They are used to transmit events

or information between processes similar to hardware interrupts[15]. The most known usecase of signals is to interrupt or terminate one processes from another one, but actually they are also used for signaling and handling errors, I/O events or to trigger even user-defined actions[1]. Signals are in common send between processes, e.g. to indicate illegal instructions or memory access, arithmetic errors, expiring timers and much more. The most of them are ignorable and/or handable by the receiving process, execpt from the SIGKILL and SIGSTOP signals[1].

Signal handlers are commonly used to grateful terminate a process or handle the indicated situation. They provide a default behaviour which can be overwritten to handle specific signals tailored to the particular process. In this case is it convention to raise the same signal with its default action again right after the custom handling finished[1]. Each Linux process is aware to receive signals, but if a signal is ignored, the result is not predictable in most cases.

Inter Process Communication

Pipes Pipes were one of the first IPC mechanisms in Unix-like systems besides shared memory between threads within a process and additional memory regions shared between processes. They provide a message-based communication mechanism using datagram-typed messages. Pipes are also in Linux wide-spread and especially known for process chaining like it is done in the command line instruction ps -A | sort | more. This instruction takes the output of the first command, ps -A (show all processes), and uses it as input to the second one, sort, which is used as input for the last one, more, again. In general, pipes can provide unidirectional or bidirectional communication between processes but ordinary Linux pipes provide only an unidirectional but buffered communication between the write-end to the read-end of a pipe[15], [39]. A bidirectional communication requires two inverse pipes [39]. As a pipe is buffered, both processes are decoupled to some degree, which is influenced by the actual buffer size, a system and architecture dependent value. Using a pipe synchronizes the involved processes implicitly. A reading process is blocked on an empty pipe, a writing one on a full pipe[15]. Ordinary Linux pipes are not accessable by another than the creating process. Thus, pipes are commonly used between a parent process and its childs or between childs. The parent creates a pipe which is inherit to forked childs [39]. For further reading, ACHILLES gives a good introduction to the implementation of Linux pipes and their usage in his book[1].

Named Pipes (FIFOs) Named pipes or FIFOs are an enhancement to the ordinary pipes described previous. In contrast to them are named pipes even between unrelated processes available. Several writers or readers on a single pipe are possible. Indeed, named pipes are capable for a bidirectional communication in half-duplex mode, too. But in fact, bidirectional IPC is done via two distinct pipes[39]. Named pipes are a special type of file which can be created with a freely selectable name at any point in a filesystem. A writing as well as a reading process can open and use a pipe by its given name just like an ordinary file or pipe[15]. Once, a named pipe was created, it exists

until it is explicitly deleted. The termination of the process which created influences the pipe just as little as a system reboot[39]. That is not the fact for ordinary pipes as the are bounded to the creating process and its childs. Both, ordinary and named pipes are only available between processes on the same system in Linux[39].

Berkeley Sockets While both types of pipes are bounded to a single system, a corresponding mechanism for cross-system communication respectively network communication is needed. The best known mechanism to do this in Linux and other Unix-like systems are Berkelev sockets. They provide cross-system communication comparable to pipes[15]. Sockets are communication endpoints, put on top of the Transmission Control Protocol (TCP) (connection-oriented) respectively the User Datagram Protocol (UDP) (connectionless) as a transportation layer and identified by an Internet Protocol (IP) address together with a port number [39]. This work will not examine the transportation layer and physical networking more closely. Using TCP, the resulting socket is called *stream socket*. The resulting communication is stream-based. In contrast, using UDP as transportation protocol, the socket is a datagram socket [39]. A communication between two processes is implemented using an own socket from the same type for each one, working according a client-server model. Sockets provide a bidirectional communication between the processes owning the endpoints with the basic operations send() and recv(). Connection-oriented sockets using TCP are additionally in need to establish a connection and shut it down as soon as it is not longer needed[15].

2.4.4 Synchronization and IPC in Zircon

Synchronization with Futexes

In Zircon, all low level synchronization mechanisms are based on futexes. High level implementations of mutexes and semaphores such as pthread_mutex_t are built on top. Thus, normal users and user applications are rarely directly in touch with futexes[29], [31]. The Zircon futex implementation is very efficient. It does not enter the kernel space or allocate any kernel resources in the uncontested case. In contrast to the Linux futex implementation do Zircon futex operations key off of the virtual address of an userspace pointer while Linux differentiate private futex actions from the ones shared across the address spaces of more than one process. Futher, Zircon futex operations do not modify the futex from the kernel, such an action is not required in the current implementation[31].

Events and Event Pairs

Events are described as signalable event for concurrent programming [12] and user signalable kernel objects [12]. A variant of events are event pairs. They are described as mutually signalable linked pairs of signalable objects for concurrent programming [27]. Unfortunately, there is not any more documentation about them and their use at all, not even in Google's zircon master repository.

Signals

Signals in Zircon are e.g. used for channels to indicate it contains messages to read. They are information exposed to applications by waitable kernel objects. Each object can expose a number of signal including generic ones for all objects but also ones that are specific to the object type such the signal described in the example above. Signals can be observed by processes respectively applications by <code>zx_object_wait_one()</code> for example. It is possible to wait for specific signals on several objects[43].

Inter Process Communication

Shared Memory Zircon provides so-called *Virtual Memory Objects (VMOs)* and VMARs which represents a contiguous region of virtual memory respectively of virtual memory address space. Both go together and are mixed up sometimes. Generally, the term VMAR is used for any operating according to address regions, e.g. allocate them, map and unmap VMOs to processes, but also to protect and destroy regions [13]. The term VMO is used for actions on the memory object, such as create one and read or write it[2]. A VMO represents a set of physical memory pages on the one hand, but also the potential for pages on-demand via lazy creation on the other. Such objects are available on both, kernel and user-space and can be mapped into the address spaces of multiple, distinct processes [2], [29]. VMARs in Zircon are randomized by default and additionally allowes adjusting the permissions of mapped pages [13]. The mapped VMOs are not only directly writeable and readable. VMOs also provide an one-shot mechanism to avoid the cost of mapping them more often into address spaces than necessary. In such a case, a VMO is created and initially written by one process and subsequently handed over to the control of another process [29]. Thus, they are very suitable for efficient IPC via shared memory.

Channels Channels are Zircon IPC objects, comparable with Pipes in Linux. But in contrast to Linux, they are bidirectional, ordered message queues with two handles, each one refers to on end of the channel. Channels provide a datagram oriented message based communication between arbitrary and unrelated processes [33], [29]. The maximum number of handles referring to a channel respectively its ends and its message size are limited. In common, there are two steps in sending a message over a Zircon channel. At first, a message is atomically written into the channel. Afterwards, the ownership of all handles in the context of the message is transferred into the channel [33]. As a result, object handles which are written into a channel are removed from the sending process. Handles which are read from a channel become added to the receiving process. During the transmission within the channel, the handle still exists to ensure the life of related objects[29]. Threads can block on a channel until messages are available. Short reads or writes are not supported. This means, messages read from or written to a channel must fit or they can not been read from or written. In contrast to pipes on Linux, Zircon channels provide a special operation called channel_call() which bundles the common situation a message is sent in one direction and its response is await right after. The sending process dequeues the matching response identified by its first four

bytes by itself[29], [33].

Sockets There are two main differences between Zircon channels and sockets. At first, sockets offer stream-oriented message passing instead of the datagram oriented one known of channels. Besides, sockets can not transfer object handles[29], [37]. Just as channels, sockets allow a bidirection communication with two ends. The data is written to one handle and read from the other one. Both ends can fulfil both jobs but they can also been shutdown for reading or writing[37]. Unlike channels, sockets provide short writes if the internal message buffer is almost filled and short reads if more data than available is requested[29].

FIFO The last IPC object Zircon provide, is a FIFO. There is no much documentation about yet, neighter in the usual documentation version used nor in Google's master repository ones. FIFOs are described as IPC queues with an advantage on read and write operations. They are intended to be a top level interface for shared memory based IPC which enables the performance advantages over channels and sockets. Nevertheless are FIFOs on Zircon more limited on the size of elements and buffers than the previously named mechanisms [22].

2.5 Scheduling

The term *scheduling* was already part of this work in the context of processes and threads. It was used to describe situations in which the actual executed processes and threads must be replaced at certain intervals to provide the impression of parallelism. In most cases, there are much more processes ready for execution than the actual number of available execution units, the CPU cores. Although this work assumes modern multicore CPUs and thus real parallelism, the number of processes in interactive or realtime operating systems is much higher than the number of cores, too. A mechanism to share the resource *computing time* between all processes being in need of it is required accordingly.

Scheduling is generally used as an umbrella term for the actual scheduling, i.e. the planning of the process execution and allocation of resources like computing time on the basis of certain criteria, and the dispatching, i.e. the mechanism which provides the assignment of a process and its data to a CPU core and executes their exchange[5], [26]. Since the concept of scheduling is already divided into strategy (policy) and mechanism, it is obvious to do this also in the implementation. The mechanism of the dispatcher is familiar from context switching. Except changing the CPU's operating mode, pure process switching follows the same rules. Basically scheduling can refer to processes in the whole or individual threads[26]. The differences and effects of both variants have already been discussed as part of the section 2.3. Scheduling strategies presented as part of this section apply to both, regardless of whether they are applied on processes or threads managed by an operating system or threads managed by a runtime environment. Thus it is often generally referred to as job scheduling[26]. Furthermore,

2.5. SCHEDULING 35

only dynamic scheduling is considered in the following. In contrast to static scheduling, changing tasks, as known from interactive or dialog driven systems, can be taken into account there. Operating systems with a fixed and static scheduling list which are setup in advanced and not changed during runtime are rare[5]. In addition, a distrinction is made between long term scheduling which describes the management of all tasks arriving in an operating system, especially the skillful execution of long-running jobs at times the system is not actively in use, and short term scheduling, the strategy to assign the processes which are currently read to run to a CPU core[5], [26].

Scheduling goals

Having the common case that more processes or, more generally spoken, jobs are ready to be executed, there is a need of a policy to find the next one to run. Such a strategy is influenced by various design goals, depending on the operating system's type, its purpose and the actual application[26]. The goals which can be included in an individual strategy are as follows:

- Fairness, i.e. a minimum computing time is guaranteed for each job and no one should be preferred if not explicitly part of the strategy.
- The *CPU utilization* should generally as high as possible. It is the most limited resource in a computing system.
- Minimize response times is especially important in interactive systems as a delayed reaction to an user input is more noticable than a longer runtime of an already long running background job.
- Minimize wait times could also be an interest. But this fact depends not only on a scheduling strategy and the related resource synchronization but also on I/O operations are not directly influenced by a job scheduler.
- Maximize throughput refers to the number of settled jobs per time.
- Minimize the turnaround time, i.e. the complete time a job needs for its execution. As with the related point "minimize wait times", a scheduling strategy only impacts the time in a waiting queue.
- A *Predictable process execution* is especially a requirement for the use in realtime operating systems[26], [5].

But there is no single scheduling strategy that fits all situations and goals equally well. In some cases, the goals named above even contradict each other. However, the decoupling of mechanism and policy enables the user to change the latter one according the current needs and interests[5].

Scheduling policies

One of the most important questions in the selection of a suitable scheduling strategy is whether it should be preemtible or not. This term was also already marginally mentioned in the context of process and thread synchronization (see section 2.3). The focus there was rather on the impact the interruptibility of a process or thread has on itself and shared resources. In the context of job scheduling, a non-preemptive job implies the job runs until it voluntary hands over the control back to the system, e.g. because it is waiting for a resource or an event or it reachs its completion [26]. Depending on the exact policy, a high maximum computation time is often given nevertheless in such a case. It prevents faulty or malicious processes from blocking an entire system[1]. Even on modern multicore CPUs is a pure non-preemptive scheduling strategy rather not suitable for interactive, multiuser and realtime operating systems, but for batch jobs. For these systems, a preemptive scheduling strategy with generally interruptible jobs is more appropriated. The whole available computing time is sliced down into equal sized time slots which are assigned to the jobs. If a job does not finish within such a slot, it needs to be rescheduled according a certail policy[5]. This makes such a system much more responsible.

The question whether a scheduling policy should be aware to priorized jobs follows directly after. There are a lot of reasons to give priority to certain jobs, e.g. to create the impression of a notably reactive system by priorize User Interface (UI) related jobs or to ensure the fastest possible processing of a security-critical task in a realtime system[26]. In general, priorized jobs are available on both, preemptive and non-preemptive policies[5].

The intention of this work is not to provide a complete enumeration of scheduling policies but a selection of relevant ones with respect to Linux and Zircon. As a consequence, preemptive strategies for interactive multiuser and realtime systems are considered in particular. More complete considerations are available in the books of BRAUSE[5], MANDL[26], ACHILLES[1] and others. For the intoduction to scheduling strategies within this work, the individual ones are examined on basis of a single CPU core. In fact do modern multicore processing systems using SMP manage an own job scheduling for each core seperately. As a result, competing situations for processes and threads such as discussed in the previous section 2.4.1 arise again. An optimal scheduling strategy for multicore systems should therefore also take the required resources into account to avoid unnecessary blocking or context changes[5]. A global component named load balancer can step in if the load on an individual core is much higher as the average[1].

Round Robin (RR) is intended for the use in interactive multiuser systems. It is an enhancement of the so-called *First Come First Serve (FCFS)* strategy used in batch-oriented systems. RR is applied for non-priorizing preemptive timesharing systems instead[1]. All reaching jobs are put into a FIFO based queue. The first one which was putted in is also the first one how gets assigned to a CPU core from the scheduler. In contrast to FCFS as a non-preemptive strategy for batch jobs, the maximum time a job is allowed to use the resource CPU is limited. Does a running

2.5. SCHEDULING 37

job not voluntary release the CPU within its time slice, an interrupt to cut it off is triggered. The job loses its CPU core which becomes reassigned to the next job in the queue. If the replaced job was not finished yet, it is enqueued again[1], [26]. The size of the time slice, also called *quantum*, is the same for each process, but the difficulty in this strategy is determination of its effective size[5]. Is the slice too small becomes the overhead caused by switching the process contexts superior, is its size choosen too long, the resulting strategy evokes on FCFS more likely. The calculation of the next job to schedule is very cheap, using RR as a strategy[5].

Dynamic Priority Round Robin (DPRR) is a priority aware modification of the usual RR scheduling strategy. The only point that differs is an additional queue in front of the known one. Each job arrives in the first queue with a priority and stay there until this value reaches a certain threshold. The priority value of each job in the preceding queue is increased after a time slices is finished. As a result a job with the priority 8 is executed prior to one with a priority of 4, even if it arrived shortly after the lower priorized one. The subsequent RR strategy is not touched at all to add priority support, but the management of the additional queue requires little more management effort[5].

Shortest Remaining Time First (SRTF) is an algorithm for preemptive scheduling with time slices, too. The decision for the next job is, as described by the name, made based on the shortest remaining computing time needed. As a result, each time a slice ends and a new job needs to be assigned to a CPU core, the remaining time for each upcoming job must be recalculated. Thus, the selection of the succeeding job is quite complex every time[5], [15].

Multilevel Scheduling is a strategy to schedule various types of jobs with different importances. The jobs are often split up into system processes with the highest priority, followed by interactive jobs and general jobs. The lowest priority is given to CPU-intensive and long-running batch jobs[5], [26]. The idea for the multilevel scheduling algorithm is to hold a distinct queue for each priority level available. Jobs in the queue with the highest priority become processed first. The ones in next lower priority are not touched until the higher ones are emptied. As a consequence are situations possible where low priority processes never become scheduled. One speaks of starvation[15]. Multilevel scheduling also allows some variants. The actual scheduling strategy for each queue itself is variable. RR can be used to provide a fair scheduling between all jobs on a single priority level. For realtime systems with one or just a few job in the highest level, fcfs could be more appropriated in certain cases. Generally is an additional reassignment of the CPU core as soon as a high priorized job enters its queue reasonable in realtime system using multilevel scheduling as a strategy[15].

Fair Share Scheduling is a strategy to guarantee the same share of the CPU to each single job. Having n jobs in the whole system, each one gets a 1/n share of the whole computing time allocated. As a result, the comuting time used so far must be

tracked along with each job. This time is compared with the actual overall time the CPU worked. The decision which job is assigned to the CPU next is made on basis of the worst ratio between already consumed computing time and the overall available one. A job scheduled according this strategy is allowed to stay active until the worst ratio is calculated for another one [26].

Earliest Deadline First [26], [5] (EDF) is a realtime scheduling strategy. Since certain critical tasks have to be completed at a given time to avoid more or less serious consequences, this algorithm uses this deadlines to decide on their basis which job must be executed next. The strategy itself is rather complex but useless in situations where several critical jobs must be completed at the same time[26], [5]. Nevertheless is EDF a common algorithm for hard realtime systems and an ideal strategy on single core systems with up to 100% CPU utilization[5].

Priority Inversion

Using locking mechanisms like semaphores respectively mutexes may lead to dangerous behaviour in context of priority based scheduling. For a basic example are two jobs, H (high priority) and L (low priority) are given. Both jobs want to use the same resource. The H job is scheduled as soon as it enters the ready state. The problem arises if the L job starts first while H is waiting for e.g. another resource. L enters the critical section and occupies the contested resource. Just in this situation, the H job becomes ready and is scheduled according to the priority based policy. If H is busy waiting for the resouce, L is never rescheduled, can not end its critical section and free the resource [45]. Both jobs are blocking each other, they are in a deadlock[15]. If H blocks and hands over to L again, the priorities got inverted. A lower priorized job runned before one with a high priority. Such a situation is referred as priority inversion [45]. The situation described here is only dangerous if the H job misses a critical deadline, but there is a very similar and serious real world example of the mars spacecraft *Pathfinder*. It also uses priority based scheduling with three jobs, H (high priority), M (medium priority, long runtime) and L (low priority). Just as explained for the situation above, the H job becomes waiting for a resource held by the L job. When H blocked, the M job was scheduled and had to finished until the L job had the chance to free the resource needed by H. But the high priorized task of H was to reset a watchdog to prevent a system reset accompanied with the loss of data[15], [39]. A more detailed description of the situation is given by SILBERSCHATZ in [39].

The most common technique to prevent dangerous *priority inversion* is *priority inheritance*, a special propery of semaphores which needs to be implemented within the operating system. If a higher priorized process or thread is waiting for a resource occupied by a less priorized, the priority of the second job will be raised to the one of the higher priorized. This ensures that the actual low prior job frees the resource as soon as possible and the truly high priorized task can run next. The original priority becomes restored, once the resource has been freed[15].

An alternative mechanism that can act without operating system support is *priority* ceiling. Whenever a process locks a semaphore or mutex, its priority is raised to a higher

2.5. SCHEDULING 39

level than any other process may waiting for the resource. As soon as the semaphore respectively mutex is unlocked, the former priority is restored[15].

2.5.1 Scheduling in Linux

As usual, modern Linux systems offer various opportunities to adjust even scheduling to the needs of its intended application. While code running in user space may be preempted at any time, common modern Linux kernels itself can be compiled in tree variants:

- As a no-forced preemption version, suitable for the use in servers.
- With voluntary kernel preemption for the use in desktop systems and
- as a fully preemtible kernel for desktop systems with low latency requirements [24], 6.

Older kernels before version 2.6.23 were not preemptible at all. They were only disturbed by explicit or implicit sleep requests, e.g. if a required resource was not available, or, if enabled, on interrupts. After the distruption, the previous task was resumed on the CPU core.

Back on modern kernel versions, one task can not interrupt another on by itself. As scheduling in Linux is based on time slices, is it the mission of the scheduler to assign another job to a CPU core as soon as a slice ends. Summarized, a job scheduled in Linux is allowed to run until

- it needs to wait for a resource to be freed or a system event to complete,
- it reaches the end of its lifetime and exits,
- its time slice expires,
- the scheduler becomes invoked and finds another job that has to be scheduled according the current policy[24].

Linux uses one scheduler per CPU core and a global load balancer to move jobs between them, just as named in the general section. However, both try to schedule a job on the same CPU to minimize cache thrashing[24].

Before kernel version 2.6.23, the default scheduler in Linux was named O(1) scheduler. It is named after the Big-O notation of its algorithm which classifies the runtime or memory requirements of algorithms according its inputs. This means in case of the O(1) scheduler that the time it needs to make the decision which task is to be scheduled next is independent of the number of tasks in the system at all. It was using a priority ordered queue for each CPU core[24]. Since kernel 2.6.23, the Completely Fair Scheduler (CFS) became the new default scheduler. It is a fair share scheduler, similar to the strategy described in the general section. The decision which task must be scheduled next is made on the basis of the amount of time a task has been waiting to run, divided

⁶See also "man 7 sched" on Linux systems as an additional source for this section.

by the number of running tasks. The resulting time of each task is compared with the actual time received so far. The one with the worst ratio is selected. Thus, the finding a decision is rather complex in this strategy[24].

Linux' origin is an interactive operating system kernel, but there was the desire to use it in realtime environments as well. For this use, the Linux kernels needed lower latencies, other preemption methods and realtime capable schedulers. As the needed changes affect wide parts of the kernel were they initially developed as a patch set called *rt preempt*. They include amongst others:

- Replacing spinlocks with preemptible *rtmutexes* in the whole kernel.
- Implementing priority inheritance for locking mechanisms.
- Replace common interrupt handlers with preemptible kernel thread so that they can be scheduled and sleep[24].

The scheduling in Linux is very finely granular adjustable to the system and its applications needs. It is not only possible to select the grade of preemptibility and make it aware for realtime tasks, but also to set a scheduling policy for each single thread. Three normal and three realtime policies are available for this purpose. The normal ones are:

- SCHED_OTHER respectively SCHED_NORMAL, as it is called within the kernel, which describes the default timesharing scheduling with a static priority level.
- SCHED_BATCH which is used to schedule CPU-intensive and non-interactive tasks. It has to be used with the static priority 0.
- SCHED_IDLE which is used for tasks with a very low priority, even lower than batch jobs.

For realtime tasks, Linux provides:

- SCHED_FIFO, a First In First Out policy just as described in the general section. It can be used with static priories greater 0. A runnable thread using this policy will immediately preempt any running task using the normal policies mentioned above.
- SCHED_RR just as mentioned in the general section is Round Robin even in Linux a timeslicing version of the FIFO policy.
- SCHED_DEADLINE is the latest scheduling policy in Linux. It is available since version 3.14 and provides a variant of the Earliest Deadline First policy mentioned in the general section combined with the Constant Bandwith Server (CBS) policy. EDF is used for the actual deadline scheduling while CBS guarantees non-interferences between threads. This strategy targets hard realtime requirements. Thread scheduled with it are the ones with the highest priority which can be controlled by a user.

2.5. SCHEDULING 41

A much more detailed explanation of thread specific scheduling policies and their use via sched() is given as part of the man-pages project using the command man 7 sched on a Linux system⁷.

2.5.2 Scheduling in Zircon

The Zircon scheduler was developed out of Little Kernel's one and provide just a minimal realtime aware scheduling mechanism instead of the variety of possibilities known from Linux. But the basic mechanims behind is also already known. Zircon scheduling is a kind of multi-level scheduling with time slicing as stated in the general section. The scheduling is done for each CPU core at its own and each core has its very own set of queues. As Zircon supports 32 priority levels right now, this makes 32 FIFO queues per core[7]. Each job gets the same time slice, if it is not finished with its work, it is enqueued again. The scheduler starts with the queue with the highest priority and executes the jobs for the maximum time of a time slice. Only when this queue is empty, the next one is considered. If a job blocks, it is completely removed from the CPU's queue and added to a distinct waiting queue. The stayes there until the required resource becomes available and thus its status changes to runnable again. The job is put back to ,whenever possibe the previous CPU core's, queue with the right priority. Was the job blocked before its time slice was finished, it becomes rewarded by beeing inserted at the front of the queue to resume as soon as possible[7].

The priority of jobs in Zircon is determined on the basis of three criteria:

- A base priority from 0 to 31.
- A priority boost.
 - A job is rewarded with an one level upgrade when it unblocks after waiting for a resource or sleeping.
 - A job is penalized with an one level downgrade if it voluntary give up the control. The minimum priority value in this situation is 0.
 - A job is penalized with an one level downgrade if it is preempted after using up its entire time slice. In this situation, the priority value may become negative.
- Priority inheritance is a special criteria. If a job controls a resource which is needed by one with a higher priority, the job's priority is temporary boosted up to the priority level of the other job to prevent priority inversion (see 2.5).

As a result, the effective priority is either calculated from the base value in combination with the boost or it is the inherit one[7]. This policy is designed for an interactive system. Rewarding short and non-CPU intensive jobs affects most of all UI related tasks which are often blocked by waiting for user interaction, while CPU intensive

 $^{^{7}}$ The man-pages version used is 2019-03-06 on a kernel in version 5.0.2.

background tasks are penalized for using the whole time slice and hindering the ability to react.

Zircon is per design capable for realtime tasks. Within the scheduler is it considered by a special flag for them: THREAD_FLAG_REAL_TIME. Such a job is allowed to run within its priority level without beein preempted until it blocks, yields or is manually rescheduled[7].

A special role belongs to the *idle thread*. It lives besides the normal FIFO queues and is runned by the scheduler if there are not any other jobs ready to be assigned. The purpose of the idle thread is to keep track of idle times, but some platform implementions may use it to implement a low power consumption wait mode[7].

At the time of writing, an additional CFS is in work. Its API is compatible to the one Linux uses. Is is not merged into the standalone Zircon repository yet, but to the development master branch of the Zircon kernel within Fuchsia. Further information is available in the according documentation within this repository⁸.

2.6 Memory Management

Memory managment is an essential part within an operating system. Without going into detail, some terms and principles belonging to this topic were already part of previous sections. For example, the topics process isolation or IPC via shared memory involved sophisticated concepts for the use of the main memory in particular. The concepts of virtual memory and private address spaces had a special significance in this context. Thus, this section will focus on them.

The reason for the use of such sophisticated memory management mechanisms over direct memory allocation is motivated by the need for process isolation, shared memory and similar approaches but also by the nature of a computer's memory. In common, the memory is a hierarchical system with CPU registers at its top. Registers are implemented in the same technology as the CPU itself. As a result, they are very limited and expensive but also very fast. The next layer are caches. Current systems use a hierarchical cache system itself. The topmost layer is nearly equivalent to registers in terms of access time and costs, and thus, very small. After two to four cache levels follows by main memory or Random Access Memory (RAM). If it is spoken about memory within this work, the main memory is meant in the majority of cases. In common, the main memory is implemented as *Dynamic RAM*. Accessing the main memory is 10 to 50 times slower than accessing caches, but the capacity is significantly larger (e.g. Intel Core i7-7820HQ; L1 caches are divided into data and instruction caches with 32 kilobyte each, while the total main memory installed is 16 gigabyte⁹[26]. The data of running processes and the system itself is generally held in the main memory. The last kind of memory which is important as a part of this

 $^{^8\}mathrm{Zircon}$ Fair Scheduler, visited on 11.04.2019 https://fuchsia.googlesource.com/fuchsia/+/refs/heads/master/zircon/docs/fair_scheduler.md

⁹Benchmarks from an Intel Core i7, 7th Generation.

thesis are common hard drives and newer Solid State Drives (SSDs), used for files, not running applications and miscellaneous other data.

As a result of this hierarchy, there is often not enough space, even not in the main memory, to store the data of all running applications. But there is a desire for allowing processes to use more memory than physically available and for a unified contiguous view of the memory area of each process together with the needs of processes, i.e. the isolation between the address spaces of distinct processes but also a way to share memory for IPC (see ?? for the details)[26], [5]. A pure static and direct memory management would not be sufficient for these purposes. In current systems, this is mostly realized using the mechanisms of address spaces and virtual memory, which already have been mentioned several times. The following sections explain what this implies.

2.6.1 Address Space

The term address space covers the summary of all possible memory addresses within the main memory from 0 to $2^{32}-1$ on a 32-bit system or $2^{64}-1$ on a 64-bit one. The address space is divided into reserved parts for the system, applications and others. How this division is done is defined by the operating system in an address space layout[26]. Distinct parts within this layout are protected against each other on base of such a layout, especially the system kernel itself[5].

But this term is also used for the memory region of applications which is effectively located within the main memory's address space. Their layout is specified by the compiler or a runtime based on language conventions or standards. A C application is for example divided into different sections like the program code itself, constants, static variables and initialised data, not initialised data, and dynamic sections for heap (data which is allocated at runtime) and stack[26].

However, the pure implementation of address spaces does not yet solve all of the needs named above. Although the address space at its whole is now subdiveded into various regions, it is not ensured that the address space of a process within is always contiguous. From a technical point of view, this is not always possible because the size of process address spaces differs and as a result, gaps which have to be filled as well arise[26]. Furthermore, data should be aligned to addresses which are divisible by four to make accessing main memory from the CPU more efficient[26], [5].

2.6.2 Virtual Memory

[26] - a process should be executed even if its memory range is not completely in ram - the memory consumption at all may become greater than the available physical memory - a programmer should see a contiguous memory region beginning with address 0 but not the real fragmentated ram used by multiple users

-> the os holds the actually needed pages in ram and the rest at hard drives -> a big program does not use all of its memory at once -> take usage of locality effects (on runtime, similar code memory and data regions are needed)

- -> a process memory is named virtual address space or virtual memory -> not physical available -> memory manager virtualizes it for each process
- virtual memory is logical memory used by a process and mapped to real one during runtime -> management is done by the os -> memory manager implements: fetch policy placement policy speicherzuteilungsstrategie replacement policy cleaning policy

fetching policy: when must a memory region be present in the ram placement -> where are new added memory pages placed within the ram replacement -> which page must be removed if there is no more free mem and a new one should come in cleaning -> tries to hold a piece in ram free at any time

- locality of reference temporal locality spartial/memory locality
- [5] abstraction to physical memory groups distict physical parts together to on contiguous area starting with address 0 enables a programm using more memory than physically available -> swapping inactive parts to disks

memory areas of virtual and physical memory are divided to blocks -> blocks from the virtual address space are referred as pages -> blocks from the physical address space are referred as page frames

- transportation of data between ram/main memory and hard drives -> demand paging -> just done if there is need for a page -> prepaging -> use of locality effects if a page is needed, its useful to load neighbouring pages to main mem too (with respect to certain algorithms)
- paging area -> disk region for outsourced pages os is responsible for which pages can be outsourced so the system can still work efficiently -> need strategies (not a topic in this place)
- [5] mechanism to implement a virtual address space -> divide the memory in blocks of the same size address and state of each page are managed in a page table. a distinct pagetable for each program is available in ram

the physical memory is also divided in pages, but size and location is distinct from the virtual memory -> named page frame

virtual addressing is supported by a hardware mechanism in modern application cpus -> mmu is a part of the processor and maps virtual addresses to physical ones cpu sends the virtual address, mmu calculates the physical one (defined algorithm) and sends them to the main memory via the address bus

is a needed page not in the main memory, the mmu raises a page fault -> running process is interrupted -> kernel tries to load the frame - process is rescheduled if the resource is available

translation lookaside buffer is a fast cache for the assignment between virtual and physical addresses -> is a part of the mmu should have faster access times than main memory -> holds references to the most used pages if an address is already in the tlb, no further main memory acceess is needed, if not, the mmu itself is needed

one tlb for each cpu replacement strategy is needed

- [5] just one mechanims for address conversation and speeding it up is tlb
- [5] virtual memory enables process isolation but also shared memory for shared libs or ipc

2.7. I/O 45

2.6.3	Memory	Management	in	Linux
[26] [br :	ause			

- 2.6.4 Memory Management in Zircon
- 2.7 I/O
- 2.7.1 I/O Hardware
- 2.7.2 Memory Mapped IO
- 2.7.3 Direct Memory Access
- 2.7.4 Interrupts
- 2.7.5 Power Management
- 2.8 Driver Models

Chapter 3

Case Study: Driver Development in Linux and Zircon

3.1	1 7	$\Gamma\!\mathrm{est}$	Set	นท
\mathbf{v}			\sim \circ	\mathbf{u}_{P}

- 3.1.1 Hardware Issues
- 3.2 General Driver Concept
- 3.3 Linux
- 3.3.1 Driver Implementation

Interface

- 3.4 Zircon
- 3.4.1 Driver

 \mathbf{C}

C++

FIDL

3.4.2 PDev Driver

 \mathbf{C}

C++

FIDL

- 3.4.3 User Application
- 3.5 Evaluation

Chapter 4

Conclusion

Chapter 5

Outlook

Bibliography

- [1] Albrecht Achilles. Betriebssysteme: eine kompakte Einführung mit Linux. Berlin: Springer, 2006. ISBN: 978-3540238058.
- [2] Christopher (cja) Anderson et al. Virtual Memory Object. Oct. 2018. URL: https://github.com/Allegra42/zircon/blob/i2c-grove-lcd/docs/objects/vm_object.md.
- [3] Mojtaba Bagherzadeh et al. "Analyzing a Decade of Linux System Calls". In: Empirical Software Engineering (Oct. 2017). DOI: 10.1007/s10664-017-9551-z.
- [4] Raghu Bharadwaj. Mastering Linux Kernel development: a kernel developer's reference manual. Birmingham, UK: Packt Publishing, 2017. ISBN: 978-1-78588-305-7.
- [5] Rüdiger Brause. Betriebssysteme: Grundlagen und Konzepte. Berlin: Springer Vieweg, 2017. ISBN: 978-3-662-54099-2.
- [6] Jonathan Corbet. *Linux device drivers*. Beijing Sebastopol, CA: O'Reilly, 2005. ISBN: 0-596-00590-3.
- [7] Ed Coyne and Bruce Mitchener. Zircon Scheduling. Dec. 2018. URL: https://github.com/Allegra42/zircon/blob/i2c-grove-lcd/docs/kernel_scheduling.md.
- [8] Matt Davis. "Creating a vDSO: the Colonel's Other Chicken". In: Linux Journal (Feb. 2012). URL: https://www.linuxjournal.com/content/creating-vdso-colonels-other-chicken.
- [9] Nick Desaulniers et al., eds. Compiling the Linux kernel with LLVM tools. Feb. 2019. URL: https://fosdem.org/2019/schedule/event/llvm_kernel/.
- [10] David Diamond and Linus Torvalds. Linus Torvalds: Just For Fun. Wie ein Freak die Computerwelt revolutionierte. Die Biographie des Linux-Erfinders. ngerman. Titel der amerikanischen Originalauflage: Just for Fun The Story of an Accidental Revolutionary. HarperCollins, New York, 2001. Aus dem Amerikanischen von Doris Märtin. München: Deutscher Taschenbuch Verlag, 2002. ISBN: 3-423-36299-5.
- [11] Jake Edge. "Building the kernel with Clang". In: Linux Plumbers Conference. Sept. 2017. URL: https://lwn.net/Articles/734071/.

[12] Todd Eisenberger, Roland McGrath, and George Kulakowski. *Event.* Sept. 2017. URL: https://github.com/Allegra42/zircon/blob/i2c-grove-lcd/docs/objects/event.md.

- [13] Todd Eisenberger et al. Virtual Memory Address Region. Oct. 2018. URL: https://github.com/Allegra42/zircon/blob/i2c-grove-lcd/docs/objects/vm_address_region.md.
- [14] Travis (travisg) Geiselbrecht et al. IRC Chat Discussion About the Zircon Microkernel (Architecture, Design Goals, Language Support). Freenode IRC. Feb. 2019.
- [15] Eduard Glatz. Betriebssysteme: Grundlagen, Konzepte, Systemprogrammierung. Heidelberg: Dpunkt, 2015. ISBN: 978-3864902222.
- [16] Richard E. Gooch. Why is the Linux kernel monolithic? Why don't we rewrite it as a microkernel? Oct. 2009. URL: http://vger.kernel.org/lkml/#s15-4.
- [17] Richard E. Gooch et al. Section 15 Programming Religion. Oct. 2009. URL: http://vger.kernel.org/lkml/#s15.
- [18] Scott Grahm and George Kulakowski. *Task.* Nov. 2018. URL: https://github.com/Allegra42/zircon/blob/i2c-grove-lcd/docs/objects/task.md.
- [19] Hermann Härtig et al. "The performance of -kernel-based systems". In: Proceedings of the sixteenth ACM symposium on Operating systems principles SOSP '97. ACM Press, 1997. DOI: 10.1145/268998.266660. URL: https://doi.org/10.1145/268998.266660.
- [20] Alan Holt. Embedded operating systems: a practical approach. London: Springer, 2014. ISBN: 978-1-4471-6602-3.
- [21] Nick Kralevich, Roland McGrath, George Kulakowski, et al. Fuchsia's libc. Mar. 2018. URL: https://github.com/Allegra42/zircon/blob/i2c-grove-lcd/docs/libc.md.
- [22] George Kulakowski. FIFO. Apr. 2017. URL: https://github.com/Allegra42/zircon/blob/i2c-grove-lcd/docs/objects/fifo.md.
- [23] George Kulakowski et al. Zircon Kernel objects. Feb. 2018. URL: https://github.com/Allegra42/zircon/blob/i2c-grove-lcd/docs/objects.md.
- [24] LFD430 Developing Linux Device Drivers. v4.19. The Linux Foundation. The Linux Foundation, 2018.
- [25] John Madieu. Linux deivce drivers development: develop customized drivers for embedded Linux. Birmingham, UK: Packt Publishing, 2017. ISBN: 978-1-78528-000-9.
- [26] Peter Mandl. Grundkurs Betriebssysteme: Architekturen, Betriebsmittelverwaltung, Synchronisation, Prozesskommunikation, Virtualisierung (German Edition). Springer Vieweg, 2014. ISBN: 9783658062170.

[27] Roland McGrath and George Kulakowski. Event Pair. Sept. 2017. URL: https://github.com/Allegra42/zircon/blob/i2c-grove-lcd/docs/objects/eventpair.md.

- [28] Roland McGrath, George Kulakowski, and Garret Kelly. Zircon vDSO. Aug. 2018. URL: https://github.com/Allegra42/zircon/blob/i2c-grove-lcd/docs/vdso.md.
- [29] Roland McGrath, George Kulakowski, Brian Swetland, et al. Zircon Kernel Concepts. Dec. 2018. URL: https://github.com/Allegra42/zircon/blob/i2c-grove-lcd/docs/concepts.md.
- [30] Roland McGrath, Carlos Pizano, and Bruce Mitchener. Zircon and LK. Oct. 2018. URL: https://github.com/Allegra42/zircon/blob/i2c-grove-lcd/docs/zx_and_lk.md.
- [31] Roland McGrath et al. Futex. Dec. 2018. URL: https://github.com/Allegra42/zircon/blob/i2c-grove-lcd/docs/objects/futex.md.
- [32] Carlos Pizano, Scott Grahm, and George Kulakowski. *Job.* Nov. 2018. URL: htt ps://github.com/Allegra42/zircon/blob/i2c-grove-lcd/docs/objects/job.md.
- [33] Carlos Pizano et al. *Channel*. Dec. 2018. URL: https://github.com/Allegra42/zircon/blob/i2c-grove-lcd/docs/objects/channel.md.
- [34] Carlos Pizano et al. *Process*. Dec. 2017. URL: https://github.com/Allegra42/zircon/blob/i2c-grove-lcd/docs/objects/process.md.
- [35] Carlos Pizano et al. *Thread*. Nov. 2018. URL: https://github.com/Allegra42/zircon/blob/i2c-grove-lcd/docs/objects/thread.md.
- [36] Richard Rashid et al. "Mach: A System Software Kernel". In: (Sept. 1992).
- [37] James Robinson et al. *Socket*. Nov. 2018. URL: https://github.com/Allegra 42/zircon/blob/i2c-grove-lcd/docs/objects/socket.md.
- [38] Rusty Russell. *Unreliable Guide To Locking*. 2016. URL: https://kernel.read thedocs.io/en/sphinx-samples/kernel-locking.html.
- [39] Abraham Silberschatz. Operating system concepts. Hoboken, NJ: J. Wiley & Sons, 2009. ISBN: 978-0470233993.
- [40] Brian Swetland et al. *Introduction*. Oct. 2017. URL: https://github.com/littlekernel/lk/wiki/Introduction.
- [41] Brian Swetland et al. Zircon. Oct. 2018. URL: https://github.com/Allegra42/zircon/blob/i2c-grove-lcd/README.md.
- [42] Brian Swetland et al. Zircon Handles. Jan. 2018. URL: https://github.com/Allegra42/zircon/blob/i2c-grove-lcd/docs/handles.md.
- [43] Brian Swetland, Roland McGrath, and George Kulakowski. *Zircon Signals*. Feb. 2018. URL: https://github.com/Allegra42/zircon/blob/i2c-grove-lcd/docs/signals.md.

[44] Andrew S. Tanenbaum. *Moderne Betriebssysteme*. Ed. by Herbert Bos. 4., aktualisierte Auflage. Always learning. Hallbergmoos: Pearson, 2016. ISBN: 978-3-86894-270-5.

- [45] Andrew S. Tanenbaum and Herbert Bos. *Modern operating systems*. 4. ed. Boston: Prentice Hall, 2015. ISBN: 978-013-359-162-0; 978-1-2920-6142-9; 0-13-359162-X.
- [46] Andrew S. Tanenbaum, Linus Torvalds, et al. *LINUX is obsolete*. Jan. 1992. URL: https://groups.google.com/d/topic/comp.os.minix/wlhw16QWltI/discussion.
- [47] Andrew S. Tanenbaum and Albert S. Woodhull. *Operating systems : design and implementation*. 3. ed. The MINIX book. Upper Saddle River, NJ: Pearson Prentice-Hall, 2006. ISBN: 978-0-13-142938-3; 0-13-142938-8; 0-13-142987-6.
- [48] Jürgen Wolf. C von A bis Z: das umfassende Handbuch; [inkl. CD-ROM mit Openbooks und Referenzkarte mit wichtigen Befehlen. Bonn: Galileo Press, 2009. ISBN: 978-3-8362-1411-7.
- [49] Jason Wu, Dan Williams, and Hakim Weatherspoon. *Microkernels: Mach and L4.* 2010. URL: https://www.cs.cornell.edu/courses/cs6410/2010fa/lectures/06-microkernels.pdf.

List of Abbreviations

\mathbf{API}	Application Programming Interface	. 11
CBS	Constant Bandwith Server	. 40
\mathbf{CFS}	Completely Fair Scheduler	. 39
CPSR	Current Program Status Register	7
CPU	Central Processing Unit.	1
DPRR	Dynamic Priority Round Robin	
EDF	Earliest Deadline First	
\mathbf{ELF}	Executable and Linking Format	. 15
FCFS	First Come First Serve	36
FIFO	First In First Out	30
futex	fast user-space mutex	. 26
GCC	GNU Compiler Collection	.12
IDL	Interface Definition Language	. 13
I/O	Input/Output	. 1
IP	Internet Protocol	32
IPC	Inter-Process Communication	9
LWP	Light-Weight Process	. 20
PC	Program Counter	. 20
PCB	Process Controll Block	. 19
PID	Process Identifier	. 21
POSIX	Portable Operating System Interface for UniX	1
PSW	Program Status Word	7
RAM	Random Access Memory	. 42
RR	Round Robin	
SMP	Symmetric Multiprocessing	8
SRTF	Shortest Remaining Time First	
SSD	Solid State Drive	43

TCP	Transmission Control Protocol	. 32
TAS	Test and Set	. 25
TCB	Thread Controll Block	. 20
TSL	Test and Set Lock	. 25
UDP	User Datagram Protocol	. 32
\mathbf{UI}	User Interface	. 36
vDSO	virtual Dynamic Shared Object	. 15
VMAR	Virtual Memory Address Region	. 23
VMO	Virtual Memory Object	. 33
XCHG	Exchange	25

List of Listings

List of Figures

2.1	The Rings of the x86's security concept[15]	7
2.2	A system calls sequence including the mode switches[15]	7
2.3	System Call Implementation[24]	14
2.4	Lifecycle of a process[39]	18

List of Tables