Getting Started with XShaderCompiler

Lukas Hermanns

December 5, 2016

Contents

I	Introduction	3
1	Prerequisites	3
	Progress2.1 ToDo List	4
3	Offline Compiler 3.1 Commands	

Part I

Introduction

1 Prerequisites

XShaderCompiler ("Cross Shader Compiler") is a cross-compiler (also called trans-compiler), which translates HLSL code (DirectX High Level Shading Language, see msdn.microsoft.com) of Shader Model 3, 4, and 5 into GLSL code (OpenGL Shading Language, see www.opengl.org).

2 Progress

This project is still in its early steps. Here is a short overview of its progress:

2.1 ToDo List

- Geometry Shader Semantic
- Tessellation Shader Semantic

3 Offline Compiler

The offline compiler (named xsc) can be used to cross-compile your shaders without building any custom application. It has similar commands like other common compilers (such as GCC), e.g. -0 to enable optimization. To show the description of all commands, type simply xsc or xsc -help into a terminal or command line.

3.1 Commands

Here is an overview of the most important commands:

-T, --target TARGET

Sets the shader target specified by TARGET. Valid values for TARGET are:

```
vert (for Vertex Shader)
```

tesc (for Tessellation Control Shader, also called Hull Shader)

tese (for Tessellation Evaluation Shader, also called Domain Shader)

geom (for Geometry Shader)

frag (for Fragment Shader, also called Pixel Shader)

comp (for Compute Shader)

-E, --entry ENTRY

Sets the shader entry point (i.e. main function) specified by ENTRY.

-I, --include-path PATH

Adds the file path, specified by PATH, to the include search paths.

-o, --output FILE

Sets the filename of the output file specified by FILE. The default value is "FILE.ENTRY.TARGET", where FILE is the filename of the input shader file, ENTRY is the shader entry point, and TARGET is the shader output target. The asterisk character '*' can be included to re-use the default value, e.g. "OutputFolder/*" will result into "OutputFolder/FILE.ENTRY.TARGET"

-Vin, --version-in VERSION

Sets the input shader version specified by VERSION. Valid values for VERSION are:

```
HLSL3 (for HLSL Shader Model 3)
```

HLSL4 (for HLSL Shader Model 4)

HLSL5 (for HLSL Shader Model 5) default value

-Vout, --version-out VERSION

Sets the output shader version specified by VERSION. Valid values for VERSION are:

GLSL (for automatic deduction of the minimal required GLSL version) default value

GLSL110 (for GLSL 1.10) not supported yet

GLSL120 (for GLSL 1.20) not supported yet

GLSL130 (for GLSL 1.30)

GLSL140 (for GLSL 1.40)

GLSL150 (for GLSL 1.50)

GLSL330 (for GLSL 3.30)

GLSL400 (for GLSL 4.00)

GLSL410 (for GLSL 4.10)

GLSL420 (for GLSL 4.20)

GLSL430 (for GLSL 4.30)

GLSL440 (for GLSL 4.40)

GLSL450 (for GLSL 4.50)

3.2 Error Output

XShaderCompiler has an extensive report handler for meaningful output messages. It even has a line marker, to show the source line where the error (or warning) occured. This can be very handy because the line marker acts like a picture, and a picture is worth a thousand words ;-) Take a look at the following example, where the slot register 'b0' uses a target specific profile (here 'vs' for the Vertex Shader):

```
compile "ErrorTest1.hlsl" to "output/ErrorTest1.VertexMain.vert"

3 ERRORS

-----
context error (ErrorTest1.hlsl:4:20) [ERR_TARGET_INVALID(X3515)]:
user-defined constant buffer slots can not be target specific
cbuffer Matrices : register(vs, b0)
```

Figure 1: Error output example of XShaderCompiler.

There are a couple of things displayed in this error message, which we will go thorugh step by step:

1. context error

This indicates that the error occured during the context analysis. The compilation phases are: *pre-processing*, *syntax parsing*, *context analysis*, *post-processing* (optimization and conversion for the target language), and *code generation*.

2. (ErrorTest1.hlsl:4:20)

The part in the brackets shows the source position in the input code. Here the filename is "ErrorTest1.hlsl", the row is 4, and the column is 20.

3. [ERR_TARGET_INVALID(X3515)]

This part does only appear in a couple of types of errors. It shows the error code, which is commonly only displayed as the number within the brackets, but the XShaderCompiler also shows the identifier.

4. **user-defined constant buffer slots can not be target specific**This is the actual error message, which describes the compilation conflict.

Here is another example how the line marker can show very intuitively what the problem is:

Figure 2: Error output example of XShaderCompiler.

Here the variable light, which is from type struct Light, can not be casted to a float3 type within a concatenation like the '+' operator.