Windows PowerShell Web Access

Windows PowerShell Web Access, introduced in Windows Server 2012, lets you configure Web Server (IIS) as a gateway, providing a web-based Windows PowerShell console targeted at a remote computer. For more information, see Install and Use Windows PowerShell Web Access (http://go.microsoft.com/fwlink/?LinkID=221050).

Install-PswaWebApplication (requires elevation)

Quick configuration of the PSWA application and application pool. The cmdlet installs the web application, pswa (and an application pool for it, pswa_pool), in the Default Web Site container that is displayed in IIS Manager. For a test environment only, add the UseTestCertificate parameter, which applies a self-signed test certificate to the website. Do not use a test certificate in any environment that should be secure.

Add-PswaAuthorizationRule (in WS12 R2, can run on remote computers with -Credential parameter)

Adds a new authorization rule. Authorizes specified users or groups access to specified session configurations on specified computers. Without authorization rules, no users can access anything by using the web-based console.

Remove-PswaAuthorizationRule

Removes a specified authorization rule from Windows PowerShell Web Access.

Get-PswaAuthorizationRule

Returns a set of Windows PowerShell Web Access authorization rules. When it is used without parameters, the cmdlet returns all rules.

Test-PswaAuthorizationRule (in WS12 R2, can run on remote computers with -Credential parameter)

Evaluates authorization rules to determine if a specific user, computer, or session configuration access request is authorized. By default, without parameters, the cmdlet evaluates all authorization rules. By adding parameters, you can specify an authorization rule or a subset of rules to test.

Function keys for Windows PowerShell Web Access

In the web-based console, some function keys are different than those in PowerShell.exe, and some function keys are not supported in the web-based console. For a complete list of shortcuts for PowerShell.exe that aren't supported in Windows PowerShell Web Access, see <u>Use the Web-based Windows PowerShell Console</u> (http://go.microsoft.com/fwlink/?Linkld=254378).

Shortcut in PS.exe	Shortcut in PSWA
Ctrl+C to cancel	Ctrl+Q or Cancel button
	Una tha History could be the one

F5 Use the History scroll buttons Alt+Space, c or Exit Click Exit, or type Exit (none) Click Save to save a session for later

Provide alternate credentials at sign-in If the credentials to manage a remote computer are different from

those you use to authenticate on the Windows PowerShell Web Access gateway, specify alternate credentials in the **Optional Connection Settings** area on the Windows PowerShell Web Access sign-in page. For detailed instructions, see <u>Use the Web-based Windows PowerShell Console</u> (http://go.microsoft.com/fwlink/?LinkId=254378).

Management Infrastructure

Quick and easy event forwarding using WS-Man:

- 1. Set up 3 types of event forwarding: Push, Pull, Source-Initiate
- 2. Event gets published in NT event log
- 3. Passed on to WS-Man (event forwarding functionality)
- 4. WS-Man forwards event to the event collector
- 5. Event collector collects events in forwarded channel of event logOne collector can scale to multiple sources and events
- More information about how to enable event forwarding:
- More information about now to enable event forwarding http://msdn.microsoft.com/en-us/library/bb870973.aspx

http://msdn.microsoft.com/en-us/library/bb8/09/3.aspx http://technet.microsoft.com/en-us/query/bb736545

Out-of-band management using WS-Man: examples

Power On		
Example		
winrm invoke RequestStateChange cimv2/CIM_ComputerSystem -		
r:http://machine:623 -a:digest -u:admin -		
p:password @{RequestedState="2"}		
Power Off		
Example		
winrm invoke RequestStateChange cimv2/CIM_ComputerSystem -		
r:http://machine:623 -a:digest -u:admin -		
p:password @{RequestedState="3"}		
Get chassis info		
Example		
winrm enumerate cimv2/CIM_Chassis -r:http://machine:623 –		
a:digest -u:admin -p: <i>password</i>		
Get operating system info		
Example		
winrm get wmicimv2/Win32_OperatingSystem		

Common remote management tasks Add servers to existing list of TrustedHosts

Add servers to existing list of Trusteuriosts		
ixample let-Item wsman:\localhost\Client\TrustedHosts Server01 - Concatenate -Force		
Create a new listener over port 5985 (for older releases of		
Vindows Server)		
ixample vinrm create winrm/config/Listener?Address=*+Transport=HTTP vinrm set winrm/config/Listener?Address=*+Transport=HTTP @{Port="5985"}		
Configure the number of maximum shells allowed per user		
ixample vinrm s winrm/config/winrs @{MaxShellsPerUser="X"}		

Management Log File Locations

Event Tracing for Windows Commo

Component	Event Tracing for Windows Channels	Comment
Server Manager console	Applications And Services Logs\Microsoft\Windows\Se rverManager-MultiMachine	Client operations events; stored on the computer that is running Server Manager
Server Manager Management Provider	\ServerManager- ManagementProvider	Events in this log are stored on the managed server
Add Roles and Features Wizard	\ServerManager- MultiMachine	
Add Roles and Features Wizard Workflow	\ServerManager- MultiMachine	Event IDs 4000-4099
Server Manager Deployment Provider	\ServerManager- DeploymentProvider	
Windows PowerShell DSC	\Microsoft-Windows-DSC	
Windows PowerShell Workflow general	\PowerShell	Event 45079 shows each activity run
Configure Remote Management task	\ServerManager- ConfigureSMRemoting	

Related Log File Locations

Component	Event Tracing for Windows Channels	
WinRM	Applications and Services Logs\Microsoft\Windows\Windows Remote Management	
WMI	\WMI-Activity	
Component-based Servicing (CBS)	%windir%\Logs	
Deployment Image Servicing and Management (DISM)	%windir%\Logs	

For detailed help about any cmdlet, including complete descriptions of all parameters, first run Update-Help, and then enter the following in a Windows PowerShell session: Get-Help <Cmdlet Name> -Full

Windows PowerShell Core Help topics online: http://go.microsoft.com/fwlink/?LinkID=238561

Windows Server Migration Portal: http://go.microsoft.com/fwlink/?LinkID=246313
Best Practices Analyzer Help: http://go.microsoft.com/fwlink/?LinkID=246313
Best Practices Analyzer Help: http://go.microsoft.com/fwlink/?LinkID=240177
Server Manager Help: http://technet.microsoft.com/fwlink/?LinkID=240177
Server Manager Help: http://technet.microsoft.com/fwlink/?LinkID=246313
Windows PowerShell Script Center: http://technet.microsoft.com/fwlink/?LinkID=240177
Server Manager Help: http://technet.microsoft.com/fwlink/?LinkID=240177
Server Manager Help: http://technet.microsoft.com/fwlink/?LinkID=221057
Cmdlet Help: http://technet.microsoft.com/fwlink/?LinkID=240177
Server Manager Help: http://technet.microsoft.com/fwlink/?LinkID=240157
Cmdlet Help: http://technet.microsoft.com/fwlink/?LinkID=240177
Server Manager Help: http://technet.microsoft.com/fwlink/?LinkID=240157
Cmdlet Help: http://technet.microsoft.com/fwlink/?LinkID=240177
Server Manager Help: http://technet.microsoft.com/fwlink/?LinkID=240157
Server Manager Help: http://technet.microsoft.com/fwlink/?LinkID=240157
Se

Manage Remote Servers

Use Server Manager in Windows Server 2012 R2 (or RSAT for Windows 8.1) to manage remote servers that are running the following operating systems, after those servers are prepared by performing the following steps. See http://go.microsoft.com/fwlink/?LinkID=241358 for more information.

Windows Server 2012 and Windows Server 2012 R2

PowerShell remote management is enabled by default. If remote management has been disabled, do one of the following: On the Local Server page of Server Manager, click Remote Management. Select Enable remote management of this server

In Windows Server 2012 and later, Server Manager and Windows

from other computers. Run the following in Windows PowerShell as an administrator: Configure-SMRemoting.exe - Enable

Windows Server 2008 R2

PowerShell remote management is disabled by default. To enable it:, do one of the following: In the **Server Summary** area of the Server Manager home page,

In Windows Server 2008 R2, Server Manager and Windows

- click Configure Server Manager Remote Management. Select Enable remote management of this server from other computers.
- Run the following Windows PowerShell script as an Administrator: Configure-SMRemoting.ps1

To manage this operating system by using Server Manager in Windows Server 2012 R2, also install the following, in the order shown:

- .NET Framework 4.5 (http://www.microsoft.com/download/details.aspx?id=30653) Windows Management Framework 4.0
- (http://go.microsoft.com/fwlink/?LinkID=293881) KB 2682011 Performance Counter Update
- (http://go.microsoft.com/fwlink/p/?LinkID=245487)

Windows Server 2008

remote management. Enable remote management of the server by running Enable-PSRemoting in a Windows PowerShell session that has been run as Administrator. Server Manager in Windows Server 2012 R2 can perform limited

In Windows Server 2008, Server Manager has no setting to enable

management on Windows Server 2008. Install the following, in the order shown. Note that WMF 4.0 cannot be installed on Windows Server 2008.

- .NET Framework 4.0 (http://go.microsoft.com/fwlink/?LinkID=212547)
- Windows Management Framework 3.0
- (http://www.microsoft.com/download/details.aspx?id=34595) KB 2682011 Performance Counter Update
- (http://go.microsoft.com/fwlink/p/?LinkID=245487)

Windows Server 2003

Server Manager is not available. To enable remote management, configure WinRM and DCOM remote management as described in Configure Remote Management

(http://go.microsoft.com/fwlink/?LinkId=252970).

Server Manager in Windows Server 2012 R2 can get only online or offline and limited data about Windows Server 2003.

Remote Management Settings

In Windows Server 2012 R2, enabling remote management by default does the following:

- Sets Windows Remote Management (WinRM) service startup type to Automatic and starts the service
- Enables **Kerberos** and **Negotiate** authentication types
- Enables inbound Windows Firewall rules for WinRM
- Changes subnet scoping rules to allow the following by default
- Domain or private profile: any IP address
- Public profile: LocalSubnet only
- Sets wsman:\localhost\Service\AllowRemoteAccess to True Creates a WinRM listener over HTTP port number 5985

The LocalAccountTokenFilterPolicy default setting prevents remote management by local, non-domain Administrator accounts other than the built-in Administrator account. For more information about remote management in Server Manager, see http://go.microsoft.com/fwlink/?LinkID=252970.

Export Server Manager Settings

To other domain-joined computers

In Active Directory Users and Computers, make the profile of a Server Manager user roaming. Open the **Properties** for a Server Manager user. On the **Profile** tab, add a path to a network share to store the user's profile. On U.S. English builds, changes to the ServerList.xml file are automatically saved to the profile. On other builds, copy these two files from the computer that is running Server Manager to the network share that is part of the user's roaming profile:

- %appdata%\Roaming\Microsoft\Windows\ServerManager\Serv
- %appdata%\Local\Microsoft Corporation\ServerManager.exe StrongName GUID\6.3.0.0\user.config

To a workgroup computer

On a computer from which you want to manage remote servers, overwrite these two files with the same files from another computer that's running Server Manager, and that has the settings you want.

- %appdata%\Roaming\Microsoft\Windows\ServerManager\Serv erList.xml
- %appdata%\Local\Microsoft_Corporation\ServerManager.exe_ StrongName_GUID\6.3.0.0\user.config

Run Minimal GUI Options

In Windows Server 2012 and later, you can switch between a server with a GUI, and Server Core or a minimal server interface option as needed. Server Manager runs without Server Graphical Shell, but does not run on Server Core. You can use Server Manager to manage remote servers running Server Core.

For more about Server Core and minimal GUI options, see Windows **Server Installation Options** (http://go.microsoft.com/fwlink/p/?LinkId=241573).

Install on Offline VHDs or VHDxs

To install features on offline VHDs or VHDxs, the VHDs must:

- Be running Windows Server 2012 R2 Not have more than one system volume or partition
- Network share containing VHD file must grant these access rights to
- the computer account of server selected to mount the VHD · Read/Write access on File Sharing dialog box.
 - Full Control access on Security tab, file or folder Properties

Install Roles and Features

In the Server Manager console

Remote Desktop Services in either a Virtual Desktop Infrastructure (VDI) or a Session Virtualization configuration, on the Select installation type page of the Add Roles and Features Wizard, select Remote Desktop installation. In the Add Roles and Features Wizard, you can install roles and features on the local server, or on a single remote server that is running Windows Server 2012 R2. See details here:

On the Manage menu, click Add Roles and Features. To deploy

Install by using deployment cmdlets (require elevation)

http://technet.microsoft.com/library/hh831809.aspx.

Get-WindowsFeature

Gets information about roles, role services, and features that are available and installed on a server. Add the ComputerName parameter to specify a server other than the local server.

Examples

Get-WindowsFeature AD*, Web* Get-WindowsFeature

Install-WindowsFeature (alias: Add-WindowsFeature)

Installs roles, role services, and features on a server that is running Windows Server 2012 R2. Add the ComputerName parameter to specify a server other than the local server. Add the Source parameter to specify an alternate location for feature files, in a Features on Demand configuration.

Examples

Install-WindowsFeature -Name Web-Server

Get-WindowsFeature Web* | Install-WindowsFeature Uninstall-WindowsFeature (alias: Remove-WindowsFeature)

Uninstalls roles, role services, and features from a computer that is running Windows Server 2012 R2. Add the Remove parameter to delete unused feature files in a Features on Demand configuration. Example

Uninstall-WindowsFeature -Name "Telnet-Client", "Telnet-Server" -Get-WindowsFeature Web* | Uninstall-WindowsFeature

Features on Demand

Run Uninstall-WindowsFeature -Remove to delete feature files from Windows Server 2012 R2 servers to save disk space. Later, you can install features by specifying a path to a remote source where feature files are stored.

- When you delete features, features that depend upon the files you remove are also deleted.
- When you delete feature files for a subfeature, and no other subfeatures for the parent feature are installed, then files for

the entire parent role or feature are deleted. For more information, see Configure Features on Demand (http://go.microsoft.com/fwlink/?LinkID=253756).

Install .NET Framework 3.5 and other Features on Demand

To install .NET Framework 3.5 or other features that have been deleted from a target server, do one of the following:

- Specify an alternate feature file repair source path
- Configure Group Policy to provide the source path automatically
- Let the installation get feature files from Windows Update.

See details here: http://go.microsoft.com/fwlink/?LinkId=253762.