

#### NAME

IPC::SharedMem - SysV Shared Memory IPC object class

### **SYNOPSIS**

```
use IPC::SysV qw(IPC_PRIVATE S_IRUSR S_IWUSR);
use IPC::SharedMem;

$shm = IPC::SharedMem->new(IPC_PRIVATE, 8, S_IRWXU);

$shm->write(pack("S", 4711), 2, 2);

$data = $shm->read(0, 2);

$ds = $shm->stat;

$shm->remove;
```

### DESCRIPTION

A class providing an object based interface to SysV IPC shared memory.

### **METHODS**

```
new (KEY, SIZE, FLAGS)
```

Creates a new shared memory segment of SIZE bytes size associated with KEY. A new segment is created if

- KEY is equal to IPC PRIVATE
- KEY does not already have a shared memory segment associated with it, and FLAGS & IPC CREAT is true.

On creation of a new shared memory segment FLAGS is used to set the permissions. Be careful not to set any flags that the Sys V IPC implementation does not allow: in some systems setting execute bits makes the operations fail.

id

Returns the shared memory identifier.

```
read (POS, SIZE)
```

Read SIZE bytes from the shared memory segment at POS. Returns the string read, or undef if there was an error. The return value becomes tainted. See *shmread*.

```
write (STRING, POS, SIZE)
```

Write SIZE bytes to the shared memory segment at POS. Returns true if successful, or false if there is an error. See *shmwrite*.

### remove

Remove the shared memory segment from the system or mark it as removed as long as any processes are still attached to it.

### is removed

Returns true if the shared memory segment has been removed or marked for removal.

stat

Returns an object of type IPC::SharedMem::stat which is a sub-class of Class::Struct



. It provides the following fields. For a description of these fields see you system documentation.

uid
gid
cuid
cgid
mode
segsz
lpid
cpid
nattch
atime
dtime
ctime

## attach ([FLAG])

Permanently attach to the shared memory segment. When a IPC::SharedMem object is attached, it will use *memread* and *memwrite* instead of *shmread* and *shmwrite* for accessing the shared memory segment. Returns true if successful, or false on error. See *shmat(2)*.

#### detach

Detach from the shared memory segment that previously has been attached to. Returns true if successful, or false on error. See *shmdt(2)*.

addr

Returns the address of the shared memory that has been attached to in a format suitable for use with pack('P'). Returns undef if the shared memory has not been attached.

# **SEE ALSO**

IPC::SysV, Class::Struct

### **AUTHORS**

Marcus Holland-Moritz <mhx@cpan.org>

# **COPYRIGHT**

Version 2.x, Copyright (C) 2007-2013, Marcus Holland-Moritz.

Version 1.x, Copyright (c) 1997, Graham Barr.

This program is free software; you can redistribute it and/or modify it under the same terms as Perl itself.