# **Assembly Language**

## What Can a Computer Understand?

- Computer can clearly NOT understand instructions of the form
  - Compute the determinant of a matrix
  - Find the shortest path between Mumbai and Delhi



## The Language of Instructions

- \* Humans can understand complicated sentences
- \* Computers can understand
  - \* Very simple instructions
  - \* The semantics of all the instructions supported by a processor is known as its *instruction set architecture* (ISA). This includes the semantics of the instructions themselves, along with their operands, and interfaces with peripheral devices.



## How to Instruct a Computer?


Program compile Executable execute Output

- Write a program in a high level language C,
   C++, Java
- \* Compile it into a format that the computer understands



\* Execute the program

## **Compilation and Assembly**



### **Compilation and Assembly**

- Write a simple program, and compile it using gcc
- The resultant a.out is in machine language, and in binary form
- Try gcc -S test.c -o test.s . test.s is the assembly program
- To get the binary from the assembly program, run gcc test.s

### Popular Instruction Set Architectures (ISAs)

x86	Laptops, desktops, servers
ARM	Mobiles, Raspberry Pi
SPARC v8	Leon3 (open project!)
PowerPC	IBM machines
RISC-V	IITM's Shakti processors
SimpleRISC	CS301
ToyRISC	CS311

#### Features of an ISA

#### \* Complete

\* It should be able to implement all the programs that users may write.

#### \* Concise

The instruction set should have a limited size.
 Typically an ISA contains 32-1000 instructions.



#### Features of an ISA – II

#### \* Generic

\* Instructions should not be too specialized, e.g. add14 (adds a number with 14) is too specialized

#### \* Simple

Should not be very complicated.



# Designing an ISA

- Important questions that need to be answered :
  - \* How many instructions should we have ?
  - What should they do ?
  - \* How complicated should they be ?



#### RISC vs CISC

A *reduced instruction set computer* (RISC) implements simple instructions that have a simple and regular structure. The number of instructions is typically a small number (64 to 128). Examples: ARM, IBM PowerPC, HP PA-RISC

A *complex instruction set computer* (CISC) implements complex instructions that are highly irregular, take multiple operands, and implement complex functionalities. Secondly, the number of instructions is large (typically

500+). Examples: Intel x86, VAX



## Let us now design an ISA ...

- Single Instruction ISA
  - sbn subtract and branch if negative

```
1: sbn a, b, 3 // a = a - b; if a < 0, jump to 3
2: sbn c, d, 3
3: sbn e, f, 1
...
```



# Let us now design an ISA ...

\* Add (a + b) (assume temp = 0)

1: sbn temp, b, 2

2: sbn a, temp, exit



# Single Instruction ISA - II

```
*
```

Mc

```
Initialization:
       one = 1
       index = 10
       sum = 0
1: sbn temp, temp, 2
                           // \text{ temp} = 0
2: sbn temp, index, 3
                           // temp = -1 * index
3: sbn sum, temp, 4
                           // sum += index
4: sbn index, one, exit
                           // index -= 1
5: sbn temp, temp, 6
                           // temp = 0
6: sbn temp, one, 1
                           // (0 - 1 < 0), hence goto 1
```

# Single Instruction ISA - II

#### \* Add the numbers – 1 ... 10

```
Initialization:
       one = 1
       index = 10
       sum = 0
1: sbn temp, temp, 2
                           // \text{ temp} = 0
2: sbn temp, index, 3
                           // temp = -1 * index
3: sbn sum, temp, 4
                           // sum += index
4: sbn index, one, exit
                           // index -= 1
5: sbn temp, temp, 6
                           // temp = 0
6: sbn temp, one, 1
                           // (0 - 1 < 0), hence goto 1
```



# Single Instruction ISA - III

#### Find whether a number is positive

- The given number is at address 'number'
- If num is positive, write '0' to address 'result'; if negative, write '-1'
- Initialization: 'one' = 1

# Single Instruction ISA - III

#### \* Find whether a number is positive

- The given number is at address 'number'
- If num is positive, write '0' to address 'result'; if negative, write '-1'
- Initialization: 'one' = 1

```
1: sbn result, result, 2 // result = 0
2: sbn temp, temp, 3 // temp = 0
3: sbn temp, number, 5 // if positive, then branch
4: sbn result, one, 5 // if negative, result = -1
5: exit
```

## Multiple Instruction ISA

#### \* Arithmetic and Logical Instructions

\* add, subtract, multiply, divide, or, and, not

#### Move instructions


Transfer values between memory locations

#### \* Branch instructions

 Move to a new program location, based on the values of some memory locations



#### Von-Neumann Architecture





# Problems with Harvard/ Von-Neumann Architectures

\* The memory is assumed to be one large array of bytes



General Rule: Larger is a structure, slower it is

\* Solution:

Have a small array of named locations (registers) that can be used by instructions



Insight: Accesses exhibit locality (tend to use the same variables frequently in the same window of time)



# Uses of Registers

- \* A CPU (Processor) contains set of registers (16-64)
- \* These are named storage locations.
- \* Typically values are loaded from memory to registers.
- Arithmetic/logical instructions use registers as input operands
- Finally, data is stored back into their memory locations.



# Example of a Program in Machine Language with Registers

```
1: r1 = mem[b] // load b
2: r2 = mem[c] // load c
3: r3 = r1 + r2 // add b and c
4: mem[a] = r3 // save the result
```

- \* r1, r2, and r3, are registers
- ★ mem → array of bytes representing memory



# Machine with Registers

