# 1 Slide 'hardware-insights'

## 1.1 OOO Pipeline execution and imprecise exceptions

When processor executes instructions in an order governed by the availability of input data and execution units, rather than by their original order in a program, we are adopting an **out-of-order execution paradigm**; in other words different instructions can surpass each other depending on data or micro-controller availability. We distinguish two events when we use this kind of paradigm: the **emission**, that is the action of injecting instructions into the pipeline; the **retire**, that is the action of committing instructions and making their side effects visible in terms of ISA exposed architectural resources

Is important to recall that out-of-order completion must preserve exception behaviour in the sense that exactly those exceptions that would arise if the program were executed in strict program order actually do arise. However, when we use OOO execution paradigm a processor may generate the so called imprecise exceptions. An exception is imprecise if the processor state when an exception is raised does not look exactly as if the instructions were executed sequentially in strict program order. In other words imprecise exceptions can occur because when:

- The pipeline may have already completed instructions that are later in program order than the instruction causing the exception.
- The pipeline may have not yet completed some instructions that are earlier in program order than the instruction causing the exception.

Recall that any instruction may change the micro-architectural state, although finally not committing its actions onto ISA exposed resources. Since the pipeline may have not yet completed the execution of instructions preceding the offending one, hardware status can been already changed an this fact can be exploited by several attacks (like Meltdown).

# 1.2 Tomasulo algorithm

Tomasulo's algorithm is a computer architecture hardware algorithm for dynamic scheduling of instructions that allows out-of-order execution and enables more efficient use of multiple execution units. Suppose two operation A and B such that A precedes B in program order, that algorithm permit to resolve three hazard:

RAW (Read After Write) B reads a datum before A writes it.

WAW (Write After Write) B writes a datum before A writes the same datum.

WAR (Write After Read) B writes a datum before A reads the same datum.

RAW hazards are avoided by executing an instruction only when its operands are available, while WAR and WAW hazards are eliminated by *register renaming* 

#### 1.3 UMA

When we have a **single main memory** that has a *symmetric relationship to all processors and a uniform access time from any processor*, these multiprocessors are most often called *symmetric shared-memory multiprocessors* (SMPs), and this style of architecture is sometimes called *uniform memory access* (UMA): in fact, all processors have a uniform latency from memory. The term shared memory refers to the fact that the address space is shared; that is, the same physical address on two processors refers to the same location in memory. In this architecture all CPUs can have one or more level of cache. However this architecture is obliviously not scalable when the number of CPUs grows.

# 1.4 NUMA

When we have a distributed memory, a multiprocessor architecture is usually called distributed shared-memory (DSM). When we use this kind of system, we have two benefits:

- A cost-effective way to scale the memory bandwidth if most of the accesses are to the local memory in the node.
- Reduces the latency for accesses to the local memory by a CPU.

The key disadvantages for that architecture is that communicating data between processors becomes more complex, and that it requires more effort in the software to take advantage of the increased memory bandwidth afforded by distributed memories.

The DSM multiprocessors are also called **NUMAs** (non-uniform memory access), since the access time depends on the location of a data word in memory. In fact, when a CPU wants to access to an item stored into his node, performing a local access involving inner private/shared caches and controllers, access latency is very low. However when a CPU wants to access to an item stored on another node, performing a remote accesses involving remote controllers and caches, latency can be very high respect to previous case.

# 1.5 The problem of cache coherence

Unfortunately, the view of memory held by different processors is through their individual caches, which, without any additional precautions, could end up seeing different values of a same shared data (cache coherence problem).

By definition, coherence defines what values can be returned by a read (a cache coherence protocols defines how to maintain coherence) while consistency determines when a written value will be returned by a read (a memory consistency protocol defines when written value must be seen by a reader).

A memory system is coherent if:

- 1. A read from location X, previously written by a processor, returns the last written value if no other processor carried out writes on X in the meanwhile. This property preserve program order that is the causal consistency along program order.
- 2. A read by a processor to location X that follows a write by another processor to X returns the written value if the read and write are sufficiently separated in time and no other writes to X occur between the two accesses. This property assure that a processor couldn't continuously read an old data value (Avoidance of staleness).
- 3. Writes to the same location are serialized; that is, two writes to the same location by any two processors are seen in the same order by all processors.

The choice and the design of a coherence protocol depends on many factors including: overhead, latency, cache policies, interconnection topology and so on. However the Key to implementing a cache coherence protocol is tracking the state of any copy of a data block. There are two classes of protocol which define when update aforementioned copies:

**Update protocol** When we use this type of protocol, also called *write update* or *write broadcast*, when a core writes to a block, it updates all other copies (it consumes considerably more bandwidth).

Invalidate protocol When we use this type of protocol, a processor has exclusive access to a data item before it writes that item; moreover that CPU invalidates other copies on a write that is no other readable or writeable copies of an item exist when the write occurs. It is the most common protocol, but suffer of some latency.

# 1.6 Snooping protocol

The key to implementing an invalidate protocol is the use of the bus, or another broadcast medium, called *network* to perform invalidates and to issue "transactions" on the state of cache blocks.

To perform any operation, the processor simply **acquires** bus access and broadcasts the address to be invalidated on the bus. All processors continuously **snoop** on the bus, watching the addresses. The processors check whether the address on the bus is in their cache. If so, the corresponding data in the cache are invalidated. A **state transition cannot occur unless the broadcast medium is acquired by the source controller and are carried out atomically with a distribute fashions thanks to <b>serialization** over the broadcast medium.

When we perform a read, we also need to locate a data item when a cache miss occurs. In a **write-through cache**, it is easy to find the recent value of a data item, since all written data are always sent to the memory, from which the most recent value of a data item can always be fetched (using write through simplifies the implementation of cache coherence). For a **write-back cache**, the problem of finding the most recent data value is harder, since the most recent value of a data item can be in a cache rather than in memory (the CPU must get data from another cache)

# 2 Slide 'kernel-level-memory-management'

# 2.1 Page Descriptor

In Linux, state information of a page frame is kept in a page descriptor of type struct page (or struct mem\_map\_t), and all page descriptors, which are 32 byte long, are stored in an array called mem\_map (the space required by it is slightly less than 1% of the whole RAM). These data structures are defined into include/linux/mm.h.

The virt\_to\_page(addr) macro yields the address of the page descriptor associated with the linear address addr. struct page has many fields but the most important are:

atomic\_t \_count It represent a usage reference counter for the page. If it is set to -1, the corresponding page frame is free and can be assigned to any process or to the kernel itself. If it is set to a value greater than or equal to 0, the page frame is assigned to one or more processes or is used to store some kernel data structures. The page\_count() function returns the value of the \_count field increased by one, that is, the number of users of the page. This field is managed via atomic updates, such as with LOCK directives.

struct list\_head lru Contains pointers to the least recently used doubly linked list of pages.

unsigned long flags Array of flags used to describe the status of current page frame (but also encodes the zone number to which the page frame belongs). There are up to 32 flags and Linux kernel defines many macros to manipulate them. Some flags are:

PG\_locked The page is locked; for instance, it is involved in a disk I/O operation.

PG\_dirty The page has been modified.

PG\_reserved The page frame is reserved for kernel code or is unusable.

#### 2.2 Free list

Linux uses free list to manage memory allocation. It operates by connecting unallocated regions of memory together in a linked list, using the first word of each unallocated region as a pointer to the next.

Free lists make the allocation and deallocation operations very simple. To free a region, one would just link it to the free list. To allocate a region, one would simply remove a single region from the end of the free list and use it.

### 2.3 NUMA

Is extremely important to remember that Linux 2.6 supports the *Non-Uniform Memory Access* (**NUMA**) model, **in which the access times for different memory locations from a given CPU may vary** and, according to that architecture, physical memory is partitioned in several **nodes**. The time needed by a given CPU to access pages within a single node is the same. However, this time might not be the same for two different CPUs.

# 2.4 NUMA Node Descriptor

Be careful that Linux splits physical memory inside each node into several zones. We have 3 free lists of frames, depending on the frame positioning within available zones (defined in include/linux/mmzone.h) which are:

ZONE\_DMA Contains page frames of memory below 16 MB, that is page frames that can be used by old ISA-based devices (*Direct Memory Access* (DMA) processors).

ZONE\_NORNMAL Contains page frames of memory at and above 16 MB and below 896 MB (direct mapped by the kernel).

ZONE\_HIGHMEM Contains page frames of memory at and above 896 MB (only page cache and user).

To represent a NUMA node, Linux uses a descriptor of type struct pg\_data\_t. All node descriptors are stored in a singly linked list, whose first element is pointed to by the pgdat\_list variable. Be careful to the fact that this data structure is used by Linux kernel even if the architecture is based on *Uniform Memory Access* (UMA): in fact Linux makes use of a single node that includes all system physical memory. Thus, the pgdat\_list variable points to a list consisting of a single element (node 0) stored in the contig\_page\_data variable.

Remember that free lists information is kept within the struct pg\_data\_t data structure. In fact the most important fields of struct pg\_data\_t are:

struct page \*node\_mem\_map Array of page descriptors of the node

struct zone [] node\_zones Array of zone descriptors of the node

# 2.5 Zone Descriptor

Obliviously each memory zone has its own descriptor of type struct zone and many fields of this data structure are used for page frame reclaiming. However, most important fields are:

struct page \* zone\_mem\_map Pointer to first page descriptor of the zone.

spinlock\_t lock Spin lock protecting the descriptor.

struct free\_area [] free\_area Identifies the blocks of free page frames in the zone

In summary, Linux has links to the memory node and to the zone inside the node that includes the corresponding page frame of type struct page.

# 2.6 Buddy allocator

The technique adopted by Linux to solve the external fragmentation problem is based on the well-known **buddy system** algorithm. All free page frames are grouped into 11 lists of blocks that contain groups of 1, 2, 4, 8, 16, 32, 64, 128, 256, 512, and 1024 contiguous page frames, respectively. The largest request of 1024 page frames corresponds to a chunk of 4 MB of contiguous RAM. We use the term **order to indicate the logarithmic size of a block**.

Assume there is a request for a group of 256 contiguous page frames (i.e., one megabyte). The algorithm checks first to see whether a free block in the 256-page-frame list exists. If there is no such block, the algorithm looks for the next larger block — a free block in the 512-page-frame list. If such a block exists, the kernel allocates 256 of the 512 page frames to satisfy the request and inserts the remaining 256 page frames into the list of free 256-page-frame blocks. If there is no free 512-page block, the kernel then looks for the next larger block (i.e., a free 1024-page-frame block). If such a block exists, it allocates 256 of the 1024 page frames to satisfy the request, inserts the first 512 of the remaining 768 page frames into the list of free 512-page-frame blocks, and inserts the last 256 page frames into the list of free 256-page-frame blocks. If the list of 1024-page-frame blocks is empty, the algorithm gives up and signals an error condition.

Linux 2.6 uses a different buddy system for each zone. Thus, in the x86 architecture, there are 3 buddy systems: the first handles the page frames suitable for ISA DMA, the second handles the "normal" page frames, and the third handles the high memory page frames. Each buddy system relies on the following main data structures:

- The mem\_map array where all page descriptors are stored. Actually, each zone is concerned with a subset of the mem\_map elements. The first element in the subset and its number of elements are specified, respectively, by the zone\_mem\_map and size fields of the zone descriptor.
- The array consisting of eleven elements of type struct free\_area, one element for each group size. As we said the array is stored in the free\_area field of the zone descriptor.

Let us consider the  $k^{th}$  element of the struct free\_area array in the zone descriptor, which identifies all the free blocks of size  $2^k$ . In this data structure there is a pointer of type struct list\_head which is is the head of a doubly linked circular list that collects the page descriptors associated with the free blocks of  $2^k$  pages. Besides the head of the list, the  $k^{th}$  element of the struct free\_area array includes also the field nr\_free, which specifies the number of free blocks of size  $2^k$  pages, and a pointer to a bitmap that keeps fragmentation information.

Recall that spin locks are used to manage mem\_map AND struct free\_area array.

To achieve better performance a little number of page frames are kept in cache to quickly satisfy the allocation requests for single page frames.

#### 2.7 API

Page frames can be requested by using some different functions and macros (APIs) (they return NULL in case of failure, a linear address of the first allocated page in case of success) which prototype are stored into #include Linux/malloc.h>. The most important are:

get\_zeroed\_page(gfp\_mask) Function used to obtain a page frame filled with zeros.

- $\_\_\mathtt{get\_free\_page}(\mathtt{gfp\_mask})$  Macro used to get a single page frame.
- \_\_get\_free\_pages(gfp\_mask, order) Macro used to request  $2^{order}$  contiguous page frames returning the linear address of the first allocated page.

free\_page(addr) This macro releases the page frame having the linear address addr.

The parameter gfp\_mask is a group of flags that specify how to look for free page frames and they are extremely important when we require page frame allocation in different contexts including:

Interrupt context allocation is requested by an interrupt handler which uses above function with GFP\_ATOMIC flag (equivalent to \_\_GFP\_HIGH) which means that the kernel is allowed to access the pool of reserved page frames: therefore the call cannot lead to sleep (that is no wait) An atomic request never blocks: if there are not enough free pages the allocation simply fails.

Process context allocation is caused by a system call using GFP\_KERNEL or GFP\_USER (both equivalent to \_\_GFP\_WAIT | \_\_GFP\_IO | \_\_GFP\_FS) according to which kernel is allowed to block the current process waiting for free page frames (\_\_GFP\_WAIT) and to perform I/O transfers on low memory pages in order to free page frames (\_\_GFP\_IO): therefore the call can lead to sleep.

### 2.8 TLB operation

Besides general-purpose hardware caches, x86 processors include a cache called *Translation Lookaside Buffers* (**TLB**) to speed up linear address translation.

When a linear address is used for the first time, the corresponding physical address is computed through slow accesses to the Page Tables in RAM. The physical address is then stored in a TLB entry so that further references to the same linear address can be quickly translated.

In a multiprocessor system, each CPU has its own TLB, called the local TLB of the CPU. Contrary to the hardware cache, the corresponding entries of the TLB need **not** be synchronized, because processes running on the existing CPUs may associate the same linear address with different physical ones.

When the cr3 control register of a CPU is modified, the hardware automatically invalidates all entries of the local TLB, because a new set of page tables is in use (page table changes). However changes inside the current page table are not automatically reflected within the TLB.

Fortunately, Linux offers several TLB flush methods that should be applied appropriately, depending on the type of page table change:

flush\_tlb\_all This flushes the entire TLB on all processors running in the system, which makes it the most expensive TLB flush operation. It is used when we have made changes into the kernel page table entries. After it completes, all modifications to the page tables will be visible globally to all processors.

flush\_tlb\_mm(struct mm\_struct \*mm) Flushes all TLB entries of the non-global pages owned by a given process that is all entries related to the userspace portion for the requested mm context. Is used when forking a new process.

flush\_tlb\_range Flushes the TLB entries corresponding to a linear address interval of a given process and is used when releasing a linear address interval of a process (when mremap() or mprotect() is used).

flush\_tlb\_page Flushes the TLB of a single Page Table entry of a given process and is used when handling a page fault.

flush\_tlb\_pgtables Flushes the TLB entries of a given contiguous subset of page tables of a given process and is called when a region is being unmapped and the page directory entries are being reclaimed

Despite the rich set of TLB methods offered by the generic Linux kernel, every microprocessor usually offers a far more restricted set of TLB-invalidating assembly language instructions. Intel microprocessors offers only two TLB-invalidating techniques: the automatic flush of all TLB entries when a value is loaded into the cr3 register and the invlpg assembly language instruction which invalidates a single TLB entry mapping a given linear address.

The architecture-independent TLB-invalidating methods are extended quite simply to multiprocessor systems. The function running on a CPU sends an Interprocessor Interrupt to the other CPUs that forces them to execute the proper TLB-invalidating function (expensive operation (direct cost) due to latency for cross-CPU coordination in case of global TLB flushes).

Remember that flush a TLB has the direct cost of the latency of the firmware level protocol for TLB entries invalidation (selective vs non-selective). Recall that flush TLB lead to **indirect cost** of refilling TLB entries and the latency experimented by MMU firmware upon misses in the translation process of virtual to physical addresses.

#### 2.8.1 When flush TLB?

As a general rule, any process switch implies changing the set of active page tables and therefore local TLB entries relative to the old page tables must be flushed; this is done automatically when the kernel writes the address of the new Page Global Directory into the cr3 control register.

Besides **process switches**, there are other cases in which the kernel needs to flush some entries in a TLB. For instance, when the kernel assigns a page frame to a User Mode process and stores its physical address into a Page Table entry, it must flush any local TLB entry that refers to the corresponding linear address (virtual addresses accessible **locally** in time-sharing concurrency). On multiprocessor systems, the kernel also must flush the same TLB entry on the CPUs that are using the same set of page tables, if any (virtual addresses accessible **globally** by every CPU/core in real-time-concurrency).

Kernel-page mapping has a *global* nature, therefore when we use vmalloc() / vfree() on a specific CPU, all the other must observer mapping updates and TLB flush is necessary.

# 3 Slide 'kernel-level-task-management'

## 3.1 Interrupt handling

Under Linux, hardware interrupts are called IRQ's (Interrupt Requests) and their management typically occurs via a two-level logic:

**Top Half** A routine that actually responds to the interrupt and do a minimal amount of work to schedule its bottom half (this operation is very fast).

Bottom Half A routine scheduled by top half which execute whatever other work is required to handle the interrupt (such as awakening processes, starting up another I/O operation, and so on)

For instance, when a network interface reports the arrival of a new packet, the top half routine just retrieves the data and pushes it up to the protocol layer; actual processing of the packet is performed in a bottom half.

The most important aspect of this setup it that it permits the *top half to service a new interrupt while the bottom half is still working*; **in fact all interrupts are enabled during execution of the bottom half**. Generally the execution of top half code is handled according to a *non-interruptible scheme* (but isn't mandatory).

This scheme permit to avoid to keep locked resources when an interrupt occurs (we may incur the risk of delaying critical actions as a spin-lock release) avoiding possible deadlocks when a slow interrupt management is hit by the activation of another one that needs the same resources. Moreover this scheme keep kernel response time small which is a very important property for many time-critical applications that expect their interrupt requests to be serviced in a few milliseconds.

### 3.2 Softings, Tasklets and work queues

Form Linux 2.6, two different mechanisms are used to implement top/bottom-half processing:

- The so-called *deferrable functions*, which we will call as **softirgs** and **tasklets**: they are very fast, but all tasklet code must be atomic.
- The Workqueues, which may have a higher latency but that are allowed to sleep.

#### 3.2.1 Softings

Softirqs are statically allocated, that is they are defined at compile time. The main data structure used to represent softirqs is the softirq\_vec array, which includes NR\_SOFTIRQS (32 entries) elements of type softirq\_action. Observer that the priority of a softirq is the index of the corresponding softirq\_action element inside the array. Some of the softirqs used in Linux are:

HI\_SOFTIRQ With priority equal to 0 (first element of array) and it handles high priority tasklets.

TIMER\_SOFTIRQ With priority equal to 1 and it is used for timer related interrupts.

Another crucial data structure for implementing the softirqs is a **per-CPU 32-bit mask describing the pending softirqs**; it is stored in the \_\_softirq\_pending field of the irq\_cpustat\_t data structure (which is one of the data structure used per each CPU in the system). To get and set the value of the bit mask, the kernel makes use of the local\_softirq\_pending(). This is way softirqs can run concurrently on several CPUs, even if they are of the same type.

During interrupt acceptance, top half routine set properly the bit mask in the \_\_softirq\_pending field and then exit.

Checks for active (pending) softirgs should be performed periodically, but without inducing too much overhead. They are performed in a few points of the kernel code.

For this purpose, Linux, for each CPU, uses the so called ksoftirqd/n kernel thread (where n is the logical number of the CPU) to manage softirqs array executing bottom halves asynchronously. Once awaken, that thread, running the ksoftirqd() function, checks softirq bit mask for pending softirqs inspecting the per-CPU field \_\_softirq\_pending. If there are no softirqs pending, the function puts the current thread in the TASK\_INTERRUPTIBLE state and invokes then the cond\_resched() function to perform a process switch; otherwise, the thread runs the softIRQ handler, running do\_softirq().

Be careful that the top half routine can set the bit mask telling that a ksoftirqd/x awaken on a CPU-core x will not process the handler associated with a given softIRQ; in this way we can **create affinity between SoftIRQs and CPU-cores in order to exploit NUMA machines**. Is also possible to set bit mask in order to build affinity on group of CPU for load balancing; **in other word is possible a multithread execution of bottom half tasks**.

#### 3.2.2 tasklet

When we use softirds not necessarily we queue bottom half task, so this setup can be even more responsive. However the queuing concept is still there for on demand usage, if required.

Tasklets are built on top of two softirqs named <code>HI\_SOFTIRQ</code> and <code>TASKLET\_SOFTIRQ</code>. Several tasklets may be associated with the same softirq, each tasklet carrying its own function. There is no real difference between the two softirqs, except that <code>do\_softirq()</code> executes <code>HI\_SOFTIRQ</code>'s tasklets before <code>TASKLET\_SOFTIRQ</code>'s tasklets.

Tasklets and high-priority tasklets are stored in the tasklet\_vec and tasklet\_hi\_vec arrays respectively and both of them include NR\_CPUS elements which are list of tasklet descriptors which are a data structure of type tasklet\_struct

Each tasklet\_struct has many fields including the state field which represents the status of current tasklet and can assume two value: TASKLET\_STATE\_SCHED (tasklet pending), TASKLET\_STATE\_RUN (tasklet is running). Using this field is possible to keep track of a specific bottom half task, related to the execution of a specific function internal to the kernel.

Linux offers many APIs to manage tasklets: for instance to allocate a new tasklet\_struct data structure and initialize is need to invoke tasklet\_init(); this function receives as its parameters the address of the tasklet descriptor, the address of your tasklet function (void (\*func)), and its optional integer argument (unsigned long) for data.

The tasklet may be selectively disabled by invoking either tasklet\_disable\_nosync() or tasklet\_disable(). Both functions increase the count field of the tasklet descriptor, but the latter function does not return until an already running instance of the tasklet function has terminated. To reenable the tasklet, use tasklet\_enable(). To activate the tasklet, you should invoke either the tasklet\_schedule() function or the tasklet\_hi\_schedule() function, according to the priority that you require for the tasklet. When a tasklet is enabled its descriptor is added at the beginning of the list pointed to by tasklet\_vec[n] or tasklet\_hi\_vec[n], where n denotes the logical number of the local CPU; then HI\_SOFTIRQ and TASKLET\_SOFTIRQ softirq are enabled (all these operation are executed with local interrupts disabled)

Remember that tasklets can be instantiated by exploiting also the following macros defined in include include/linux/interrupt.h:

- DECLARE\_TASKLET(tasklet, function, data)
- DECLARE\_TASKLET\_DISABLED(tasklet, function, data)

Finally to execute tasklet associated with the HI\_SOFTIRQ softirq we run tasklet\_hi\_action(), while for those associated with TASKLET\_SOFTIRQ we use tasklet\_action().

#### 3.3 Timers

On the x86 architecture, the kernel must explicitly interact with several kinds of clock circuits which are used both to keep track of the current time of day and to make precise time measurements. The timer circuits are programmed by the kernel, so that they issue interrupts at a fixed, predefined frequency; such periodic interrupts are crucial for implementing the software timers used by the kernel and the user programs.

Time Stamp Counter (TSC) It is a counter accessible through the 64-bit *Time Stamp Counter* (TSC) register, which can be read using rdtsc assembly language instruction. It represents a counter that is increased at each clock signal. It is used by Linux to determine the clock signal frequency while initializing the system; that task is accomplished using calibrate\_tsc().

High Precision Event Timer (HPET) The HPET represents a very powerful chip which provides up to eight 32-bit or 64-bit independent counters exploitable by kernel. Each counter is driven by its own clock signal, whose frequency must be at least 10 MHz and, therefore, the counter is increased at least once in 100 nanoseconds. Any counter is associated with at most 32 timers, each of which is composed by a comparator and a match register. The comparator is a circuit that checks the value in the counter against the value in the match register, and raises a hardware interrupt if a match is found. Some of the timers can be enabled to generate a periodic interrupt.

**LAPIC** The Local APIC Timer (LAPIC-T) represents another time-measuring device. This timer has a counter of **32 bits long** used to store the number of of ticks that must elapse before the interrupt is issued; therefore, the local timer can be programmed to issue interrupts at very low frequencies. **Observe that local APIC timer sends an interrupt only to its processor**. The APIC's timer is based on the bus clock signal and can be can be programmed in such a way to decrease the timer counter every 1, 2, 4, 8, 16, 32, 64, or 128 bus clock signals.