

A Typst package for diagrams with lots of arrows, built on top of CeTZ.


Commutative diagrams, finite state machines, block diagrams...


github.com/Jollywatt/typst-fletcher


Version 0.4.1

Contents

Getting started	3
Nodes	4
Elastic coordinates	4
Fractional coordinates	4
Node shapes	5
Edges	5
Implicit coordinates	5
Relative coordinates	6
Edge types	6
The defocus adjustment	6
Marks and arrows	7
Adjusting marks	7
Hanging tail correction	8
CeTZ integration	9
Bézier edges	9
Node groups	9
Function reference	11
diagram	11
edge	14
interpret-edge-args	21
node	21
compute-grid	24
expand-fractional-rects	24
Marks	25
interpret-mark	25
interpret-marks-arg	25
round-arrow-cap-offset	26
Utilities	26
get-arc-connecting-points	26







Getting started

Avoid importing everything with * as many internal functions are also exported.

```
#import "@preview/fletcher:0.4.1" as fletcher: node, edge
// You can specify nodes in math-mode, separated by `&`:
#fletcher.diagram($
  G edge(f, ->) edge("d", pi, ->>) & im(f) \
  G slash ker(f) edge("ur", tilde(f), "hook-->")
// Or you can use code-mode, with variables, loops, etc:
#fletcher.diagram(spacing: 2cm, {
 let (A, B) = ((0,0), (1,0))
  node(A, $cal(A)$)
  node(B, $cal(B)$)
  edge(A, B, $F$, "->", bend: +35deg)
  edge(A, B, $G$, "->", bend: -35deg)
  let h = 0.2
  edge((.5,-h), (.5,+h), $alpha$, "=>")
#fletcher.diagram(
                                                                                    F(s)
                       // show a coordinate grid
  debug: true,
  axes: (ltr, btt),
                       // make y-axis go ↑
  spacing: (8mm, 3mm), // wide columns, narrow rows
  node-stroke: 1pt,
                       // outline node shapes
                                                                                    G(s)
                       // make lines thicker
  edge-stroke: 1pt,
                       // make arrowheads smaller
  mark-scale: 60%,
  edge((-2,0), (-1,0)),
  edge((-1,0), (0,+1), $f$, "..|>", corner: right),
  edge((-1,0), (0,-1), $g$, "-|>", corner: left),
  node((0,+1), F(s)),
  node((0,-1), $G(s)$),
  edge((0,+1), (1,0), "..|>", corner: right), edge((0,-1), (1,0), "-|>", corner: left),
 node((1,0), text(white, $ plus.circle $), inset: 1pt, fill: black),
  edge((1,0), (2,0), "-|>"),
)
An equation $f: A -> B$ and \
                                                                        An equation f: A \to B and
an inline diagram #fletcher.diagram(
  node-inset: 4pt,
                                                                       an inline diagram A
  label-sep: 2pt,
  $A edge(->, text(#0.8em, f)) & B$
#fletcher.diagram(
  node-stroke: black + 0.5pt,
                                                                                                   3a
  node-fill: gradient.radial(white, blue, center: (40%, 20%),
                             radius: 150%),
  spacing: (15mm, 8mm),
                                                                              go
  node((0,0), [1], extrude: (0, -4)), // double stroke effect
  node((1,0), [2]),
  node((2,-1), [3a]),
  node((2,+1), [3b]),
  edge((0,0), (1,0), [go], "->"),
  edge((1,0), (2,-1), "->", bend: -15deg),
  edge((1,0), (2,+1), "->", bend: +15deg),
  edge((2,+1), (2,+1), "->", bend: -130deg, label: [loop!]),
                                                                                                 loop!
```

Nodes

```
node((x, y), label, ..options)
```

Nodes are content centered at a particular coordinate. They automatically fit to the size of their label (with an inset and outset). They can be given a stroke and fill and be of any shape.

By default, the coordinates (x, y) are x going \rightarrow and y going \uparrow . This can be changed with the axis option of diagram().

```
#fletcher.diagram(
  debug: 1,
  spacing: (1em, 4em), //(x, y)
  node((0,0), $f$),
  node((1,0), $f$, stroke: 1pt),
  node((2,0), $f$, stroke: 1pt, shape: rect),
  node((3,0), $f$, stroke: 1pt, radius: 6mm, extrude: (0, 3)),
    let b = blue.lighten(70%)
   node((0,1), `xyz`, fill: b, )
    let dash = (paint: blue, dash: "dashed")
                                                                   XYZ
                                                                                       xyz
                                                                                                 xyz
   node((1,1), `xyz`, stroke: dash, inset: 2em)
   node((2,1), xyz, fill: b, stroke: blue, extrude: (0, -2))
   node((3,1), `xyz`, fill: b, height: 5em, corner-radius: 5pt)
 }
)
```

Elastic coordinates

Diagrams are laid out on a flexible coordinate grid. When a node is placed, the rows and columns grow to accommodate the node's size, like a table. See the diagram() parameters for more control: cell-size is the minimum row and column width, and spacing is the gutter between rows and columns.

Elastic coordinates can be demonstrated more clearly with a debug grid and no spacing between cells:


```
#let c = (orange, red, green, blue).map(x => x.lighten(50%))
#fletcher.diagram(
    debug: 1,
    spacing: 0pt,
    node-corner-radius: 3pt,
    node((0,0), [a], fill: c.at(0), width: 10mm, height: 10mm),
    node((1,0), [b], fill: c.at(1), width: 5mm, height: 5mm),
    node((1,1), [c], fill: c.at(2), width: 20mm, height: 5mm),
    node((0,2), [d], fill: c.at(3), width: 5mm, height: 10mm),
```

So far, this is just like a table. However, coordinates can also be fractional.

Fractional coordinates

Rows and columns are at integer coordinates, but nodes may have fractional coordinates. These are dealt with by linearly interpolating the diagram between what it would be if the coordinates were rounded up or down. Both the node's position and its influence on row/column sizes are interpolated.

For example, see how the column sizes change as the green box moves from (0,0) to (1,0):



Node shapes

By default, nodes are circular or rectangular depending on the aspect ratio of their label. The shape option accepts rect, circle, various shapes provided in the fletcher.shapes submodule, or can be a custom drawing function.

```
#import fletcher: shapes
#let theme = rgb("8cf")

#fletcher.diagram(
    node-fill: gradient.radial(white, theme, radius: 100%),
    node-stroke: theme,
    (
        node((0,0), [Blue Pill], shape: shapes.pill),
        node((1,0), [House], shape: shapes.house),
        node((0,1), [Choice], shape: shapes.diamond),
        node((1,1), [Stop], shape: shapes.hexagon,
        extrude: (-3, 0), inset: 1.5em),
    ).intersperse(edge("o--|>")).join()
}
```

Custom shapes can be specified with a drawing function; see the shape option of node() for details.

Edges

```
edge(from, to, label, marks, ..options)
```

Edges connect two coordinates. If there is a node at an endpoint, the edge attaches to the nodes' bounding shape. Edges can have labels, can bend into arcs, and can have various arrow marks.

```
#fletcher.diagram(spacing: (12mm, 6mm), {
                                                                              A \times B \times C
  let (a, b, c, abc) = ((-1,0), (0,1), (1,0), (0,-1))
  node(abc, $A times B times C$)
  node(a, $A$)
                                                                                                        C
  node(b, $B$)
  node(c, $C$)
  edge(a, b, bend: -10deg, "dashed")
                                                                                   B
  edge(c, b, bend: +10deg, "<-<<")
  edge(a, abc, $a$)
  edge(b, abc, "<=>")
  edge(c, abc, $c$)
                                                                                    ····· just a thought...
  node((0.6, 3), [_just a thought..._])
  edge((0.6, 3), b, "..|>", corner: right)
})
)
```

Implicit coordinates

To specify the start and end points of an edge, you may provide both explicitly (edge(from, to)); leave from implicit (edge(to)); or leave both implicit. When from is implicit, it becomes the coordinate of the last node, and to becomes the next node.


```
#fletcher.diagram( London node((0,0), [London]), edge("..|>", bend: 20deg), node((1,1), [Paris]), Paris
```

Implicit coordinates can be handy for diagrams in math-mode:

```
#fletcher.diagram($ L edge("->", bend: #30deg) & P $) L \qquad \qquad L \qquad P
```

However, don't forget you can also use variables in code-mode to avoid repeating coordinates:

```
#fletcher.diagram(node-fill: blue, {
  let (dep, arv) = ((0,0), (1,1))
  node(dep, text(white)[London])
  node(arv, text(white)[Paris])
  edge(dep, arv, "==>", bend: 40deg)
})
```



Relative coordinates


It can also be handy to specify the direction of an edge, instead of its end coordinate. This can be done with edge((x, y), (rel: (Δ x, Δ y))). For convenience, you can also specify a relative coordinate with string of *directions*, e.g., "u" for up or "br" for bottom right. Any combination of top/up/north, bottomp/down/south, left/west, and right/east are allowed. Together with implicit coordinates, this allows you do to things like:

```
#fletcher.diagram($ A edge("rr", ->, bend: #30deg) & B & C $ A B
```

Edge types

Currently, there are three different kinds of edges: "line", "arc", and "poly". All nodes have a start and end point (from and to), and "poly" edges can also have an array of additional vertices. The kind defaults to "arc" if a bend is specified, and to "poly" if any vertices are given.

```
#fletcher.diagram(
  debug: 1,
  edge((0,0), (1,1), "->", `line`),
  edge((2,0), (3,1), "->", bend: -30deg, `arc`),
  edge((0,2), (3,3), vertices: ((1,2), (2,3)), "->", `poly`),
)
```



An alternative way to specify vertices is by providing multiple coordinates: edge(A, B, C, D) is the same as edge(from: A, to: D, vertices: (B, C)) if the arguments are all coordinates. An edge's vertices and to coordinates can be relative (see above), so that the "poly" edge above could also be written in these ways:

```
edge((0,2), (rel: (1,0)), (rel: (1,1)), (rel: (1,0)), "->", `poly`)
edge((0,2), "r", "rd", "r", "->", `poly`) // use relative coordinate names
edge((0,2), "r,rd,r", "->", `poly`) // shorthand
```

The defocus adjustment

For aesthetic reasons, lines connecting to a node need not focus to the node's exact center, especially if the node is short and wide or tall and narrow. Notice the difference the figures below. "Defocusing" the connecting lines can make the diagram look more comfortable.




Figure 1: With defocus





Figure 2: Without defocus

See the node-defocus argument of diagram() for details.

Marks and arrows

A few mathematical arrow heads are supported, designed to match \rightarrow , \Rightarrow , \Rightarrow , \mapsto , \rightarrow , etc.



Some other marks are supported, and can be placed anywhere along the edge.

All the mark shorthands are defined in fletcher. MARK ALIASES and fletcher. MARK DEFAULTS:

Edge styles can be specified with a shorthand like edge(a, b, "-->"). See the marks argument of edge() for details.

Adjusting marks

While shorthands exist for specifying marks and stroke styles, finer control is possible.

```
#fletcher.diagram(
  edge-stroke: 1.5pt,
  spacing: 3cm,
  edge((0,0), (-0.1,-1), bend: -10deg, marks: (
      (kind: ">>", size: 6, delta: 70deg, sharpness: 45deg),
      (kind: "bar", size: 1, pos: 0.5),
      (kind: "head", rev: true),
      (kind: "solid", rev: true, stealth: 0.1, paint: red.mix(purple)),
    ), stroke: green.darken(50%))
```

Shorthands like "<->" expand into specific edge() options. For example, edge(a, b, "|=>") is equivalent to edge(a, b, marks: ("bar", "doublehead"), extrude: (-2, 2)). Mark names such as "bar" or "doublehead" are themselves shorthands for dictionaries defining the marks' parameters. These parameters can be retrieved from the mark name as follows:

```
#fletcher.interpret-mark("doublehead")
// In this particular example:
                                                                               size: 10.56,
// - `kind` selects the type of arrow head
                                                                               sharpness: 19deg,
// - `size` controls the radius of the arc
                                                                               delta: 43.7deg,
// - `sharpness` is (half) the angle of the tip
                                                                               outer-len: 5.5,
// - `delta` is the angle spanned by the arcs
// - `tail` is approximately the distance from the cap's tip to
                                                                               kind: "head",
// the end of its arms. This is used to calculate a "tail hang"
                                                                             )
     correction to the arrowhead's bearing for tightly curved edges.
// Distances are multiples of the stroke thickness.
```

Finally, the fully expanded version of a marks shorthand can be inspected by invoking <u>interpret-marks-arg()</u>:

```
#fletcher.interpret-marks-arg("|=>")
                                                                         marks: (
// `edge(..args, marks: "|=>")` is equivalent to
                                                                           (
// `edge(..args, ..fletcher.interpret-marks-arg("|=>"))`
                                                                             size: 4.9,
                                                                             angle: Odeg,
                                                                             pos: 0,
                                                                             rev: true,
                                                                             kind: "bar",
                                                                           ),
                                                                             size: 10.56,
                                                                             sharpness: 19deg,
                                                                             delta: 43.7deg,
                                                                             outer-len: 5.5,
                                                                             pos: 1,
                                                                             rev: false,
                                                                             kind: "head",
                                                                         ),
                                                                         extrude: (-2, 2),
```

You can customise these basic marks by adjusting these parameters. For example:

```
#let my-head = (kind: "head", sharpness: 4deg, size: 50, delta: 15deg)
#let my-bar = (kind: "bar", extrude: (0, -3, -6))
#let my-solid = (kind: "solid", sharpness: 45deg)
#fletcher.diagram(
  edge-stroke: 1.4pt,
  spacing: (3cm, 1cm),
  edge((0,0), (1,0), marks: (my-head, my-head + (sharpness: 20deg))),
  edge((0,1), (1,1), marks: (my-bar, my-solid + (pos: 0.8), my-solid)),
)
```

The particular marks and parameters are hard-wired and will likely change as this package is updated (so they are not documented). However, you are encouraged to use the functions interpret-marks-arg() and interpret-mark() to discover the parameters for finer control.

Hanging tail correction

All marks accept an outer-len parameter, the effect of which can be seen below:

```
#fletcher.diagram(
  edge-stroke: 2pt,
  spacing: 2cm,
  debug: 4,

edge((0,0), (1,0), stroke: gray, bend: 90deg, label-pos: 0.1, label: [without],
  marks: (none, (kind: "solid", outer-len: 0))),
  edge((0,1), (1,1), stroke: gray, bend: 90deg, label-pos: 0.1, label: [with],
  marks: (none, (kind: "solid"))), // use default hang
)
```

The tail length (specified in multiples of the stroke thickness) is the distance that the arrow head visually extends backwards over the stroke. This is visualised by the green line shown above. The mark is rotated so that the ends of the line both lie on the arc.

CeTZ integration

Fletcher's drawing cababilities are deliberately restricted to a few simple building blocks. However, an escape hatch is provided with the render argument of diagram() so you can intercept diagram data and draw things using CeTZ directly.

Bézier edges

Currently, only straight, arc and right-angled connectors are supported. Here is an example of how you might hack together a Bézier connector using the same functions that fletcher uses internally to anchor edges to nodes:

```
#fletcher.diagram(
                                                                                                Bézier
  node((0,1), $A$),
  node((2,0), [Bézier], fill: purple.lighten(80%)),
  render: (grid, nodes, edges, options) => {
    // cetz is also exported as fletcher.cetz
    cetz.canvas({
                                                                             \boldsymbol{A}
      // this is the default code to render the diagram
      fletcher.draw-diagram(grid, nodes, edges, options)
      // retrieve node data by coordinates
      let n1 = fletcher.find-node-at(nodes, (0,1))
      let n2 = fletcher.find-node-at(nodes, (2,0))
      let out-angle = 0deg
      let in-angle = -90 deg
      fletcher.get-node-anchor(n1, out-angle, p1 => {
        fletcher.get-node-anchor(n2, in-angle, p2 => {
          // make some control points
          let c1 = (to: p1, rel: (out-angle, 15mm))
          let c2 = (to: p2, rel: (in-angle, 30mm))
          cetz.draw.bezier(
            p1, p2, c1, c2,
            mark: (end: ">") // cetz-style mark
        })
      })
    })
 }
```

Node groups

Here is another example of how you could automatically draw "node groups" around selected nodes. First, we find all nodes of a certain fill, get their actual coordinates, and then draw a rectangle around their bounding box.

```
#let in-group = orange.lighten(60%)
#let out-group = blue.lighten(60%)
// draw a blob around nodes
#let enclose-nodes(nodes, clearance: 8mm) = {
  let points = nodes.map(node => node.real-pos)
  let (center, size) = fletcher.bounding-rect(points)
  cetz.draw.content(
    center,
    rect(
      width: size.at(0) + 2*clearance,
      height: size.at(1) + 2*clearance,
      radius: clearance,
      stroke: in-group,
      fill: in-group.lighten(85%),
 )
}
#fletcher.diagram(
  node((-1,0), \alpha), fill: out-group, radius: 5mm),
  edge("o-o"),
  node((0, 0), \beta), fill: in-group, radius: 5mm),
  edge("o-o"),
  node((1,.5), `γ`, fill: in-group, radius: 5mm),
  edge("o-o"),
  node((1,-1), \delta), fill: out-group, radius: 5mm),
  render: (grid, nodes, edges, options) => {
   // find nodes by color
    let group = nodes.filter(node => node.fill == in-group)
    cetz.canvas({
      enclose-nodes(group) // draw a node group in the background
      fletcher.draw-diagram(grid, nodes, edges, options)
    })
 }
)
```

δ

Function reference

diagram()

Draw an arrow diagram.

Parameters

```
diagram(
  ..objects: array,
  debug: bool 1 2 3,
  axes: pair of directions,
  spacing: length pair of lengths,
  cell-size: length pair of lengths,
  edge-stroke: stroke,
  node-stroke: stroke none,
  edge-corner-radius: length none,
  node-corner-radius: length none,
  node-inset: length pair of lengths,
  node-outset: length pair of lengths,
  node-fill: paint,
  node-defocus: number,
  label-sep: length ,
  mark-scale: length,
 crossing-fill: paint,
  crossing-thickness: number,
 render: function
)
```

.. objects array

An array of dictionaries specifying the diagram's nodes and connections.

The results of node() and edge() can be joined, meaning you can specify them as separate arguments, or in a block:

```
#fletcher.diagram(
  // one object per argument
  node((0, 0), $A$),
  node((1, 0), $B$),
  {
     // multiple objects in a block
     // can use scripting, loops, etc
     node((2, 0), $C$)
     node((3, 0), $D$)
  },
)
```

```
debug bool or 1 or 2 or 3
```


Level of detail for drawing debug information. Level 1 shows a coordinate grid; higher levels show bounding boxes and anchors, etc.

Default: false

axes pair of directions

The directions of the diagram's axes.

This defines the orientation of the coordinate system used by nodes and edges. To make the y coordinate increase up the page, use (ltr, btt). For the matrix convention (row, column), use (ttb, ltr).



spacing length or pair of lengths

Gaps between rows and columns. Ensures that nodes at adjacent grid points are at least this far apart (measured as the space between their bounding boxes).

Separate horizontal/vertical gutters can be specified with (x, y). A single length d is short for (d, d).

Default: 3em

cell-size length or pair of lengths

Minimum size of all rows and columns. A single length d is short for (d, d).

Default: Opt

edge-stroke stroke

Default value of the stroke option for edge(). By The default value for this option is chosen relative to the font size to match the thickness of mathematical arrows such as $A \to B$.

The default stroke is folded with the stroke specified for the edge. For example, if edge-stroke is lpt and the edge option stroke is red, then the resulting stroke is lpt + red.

Default: 0.048em

node-stroke stroke or none

Default value of the stroke option for node().

The default stroke is folded with the stroke specified for the node. For example, if node-stroke is lpt and the node option stroke is red, then the resulting stroke is lpt + red.

Default: none

edge-corner-radius length or none

Default value of the corner-radius option for edge().

Default: 2.5pt

node-corner-radius length or none

Default value of the corner-radius option for node().

Default: none

node-inset length or pair of lengths

Default value of the inset option for edge().

Default: 12pt

node-outset length or pair of lengths

Default value of the outset option for edge().

Default: Opt


node-fill paint

Default fill for all nodes in diagram. Overridden by individual node options.

Default: none

node-defocus number

Default strength of the "defocus" adjustment for nodes. This affects how connectors attach to non-square nodes. If 0, the adjustment is disabled and connectors are always directed at the node's exact center.



label-sep length

Default value of label-sep option for edge().

Default: 0.2em

mark-scale length

Default value of mark-scale option for edge().

Default: 100%

crossing-fill paint

Color to use behind connectors or labels to give the illusion of crossing over other objects. See the crossing-fill option of edge().

Default: white

crossing-thickness number

Default thickness of the occlusion made by crossing connectors. See the crossing-thickness option of edge().

Default: 5

render function

After the node sizes and grid layout have been determined, the render function is called with the following arguments:

- grid: a dictionary of the row and column widths and positions;
- nodes: an array of nodes (dictionaries) with computed attributes (including size and physical coordinates);
- edges: an array of connectors (dictionaries) in the diagram; and
- options: other diagram attributes.

This callback is exposed so you can access the above data and draw things directly with CeTZ.

```
Default: (grid, nodes, edges, options) => {
    cetz.canvas(
        draw-diagram(grid, nodes, edges, options)
    )
}
```

edge()

Draw a connecting line or arc in an arrow diagram.

Parameters

```
edge(
  ..args: any,
  vertices,
  label: content,
  label-side: left right center,
  label-pos: number,
  label-sep: number,
  label-anchor: anchor,
  stroke: stroke,
  dash: dash type,
  kind,
  bend: angle,
  corner,
  corner-radius: length none,
  marks: pair of strings,
  mark-scale: percent,
  extrude: array,
  crossing: bool,
  crossing-thickness: number,
  crossing-fill: paint,
  dodge
)
```

..args any

Positional arguments may specify the edge's:

- start and end nodes
- · any additional vertices
- label
- marks

The start and end nodes must come first, and are optional:

```
edge(from, to, ..) // explicit start and end nodes
edge(to, ..) // start node chosen automatically based on last node specified
edge(..) // both nodes chosen automatically depending on adjacent nodes
edge(from, v1, v2, ..vs, to, ..) // a multi-segmented edge
```

All coordinates except the start point can be relative (a dictionary of the form (rel: $(\Delta x, \Delta y)$) or a string containing the characters $\{l, r, u, d, t, b, n, e, s, w\}$).

Some named arguments, including marks, label, and vertices can be also be specified as positional arguments. For example, the following are equivalent:

```
edge((0,0), (1,0), $f$, "->")
edge((0,0), (1,0), $f$, marks: "->")
edge((0,0), (1,0), "->", label: $f$)
edge((0,0), (1,0), label: $f$, marks: "->")
```

Additionally, some common options are given flags that may be given as string positional arguments. These are "dashed", "double", "triple", and "crossing".

vertices

Default: ()

label content

Content for the edge label. See the label-pos and label-side options to control the position (and label-sep and label-anchor for finer control).

Default: none

label-side left or right or center

Which side of the connector to place the label on, viewed as you walk along it from base to tip. If center, then the label is place over the connector. When auto, a value of left or right is chosen to automatically so that the label is

- roughly above the connector, in the case of straight lines; or
- on the outside of the curve, in the case of arcs.

Default: auto

label-pos number

Position of the label along the connector, from the start to end (from 0 to 1).

Default: 0.5

label-sep number

Separation between the connector and the label anchor.

With the default anchor ("bottom"):



With label-anchor: "center":



Default: auto

label-anchor anchor

The anchor point to place the label at, such as "top-right", "center", "bottom", etc. If auto, the anchor is automatically chosen based on label-side and the angle of the connector.

Default: auto

stroke stroke

Stroke style of the edge. Arrows scale with the stroke thickness.

Default: auto

dash dash type

The stroke's dash style. This is also set by some mark styles. For example, setting marks: "<..>" applies dash: "dotted".


Default: none

kind

Default: auto

bend angle

Edge curvature. If Odeg, the connector is a straight line; positive angles bend clockwise.



Default: Odeg

corner

Default: none

corner-radius

length or none

Radius of rounded corners for edges with multiple segments. Note that none is distinct from Opt.







This length specifies the corner radius for right-angled bends. The actual radius is smaller for acute angles and larger for obtuse angles to balance things visually. (Trust me, it looks naff otherwise.)

If auto, defaults to the diagram() option edge-corner-radius.

Default: auto

marks pair of strings

The marks (arrowheads) to draw along an edge's stroke. This may be:

• A shorthand string such as " -> " or "hook' -/ ->> ". Specifically, shorthand strings are of the form M_1LM_2 or $M_1LM_2LM_3$, where

$$M_i \in \{\texttt{>}, \texttt{<}, \texttt{>>}, \texttt{<<}, \texttt{>>}, \texttt{<<}, \texttt{|>}, \texttt{<}|, \texttt{||}, \texttt{|||}, \texttt{|||}, \texttt{/}, \texttt{\backslash}, \texttt{x}, \texttt{X}, \texttt{o}, \texttt{0}, \texttt{*}, \texttt{@}, \texttt{}>, \texttt{<}\} \cup N$$

is a mark symbol and $L \in \{-,--,...,=,==\}$ is the line style. The mark symbol can also be a name, $M_i \in N = \{\mathsf{hook},\mathsf{hook'},\mathsf{harpoon},\mathsf{harpoon'},\mathsf{head},\mathsf{circle},...\}$ where a trailing ' means to reflect the mark across the stroke.

• An array of marks, where each mark is specified by name or by a dictionary of parameters.

Shorthands are expanded into other arguments. For example, edge(p1, p2, "=>") is short for edge(p1, p2, marks: (none, "head"), "double"), or more precisely, edge(p1, p2, ...fletcher.interpret-marks-arg("=>")).


Arrow	marks
\longrightarrow	"->"
≫ →	">>>"
\iff	"<=>"
\Longrightarrow	"==>"
	"->>-"
× / •	"x-/-@"
·····	"[]"
←	"hook->>"
	"hook'->>"
₩•	" -*-harpoon'"
\longrightarrow	("X", (kind: "head", size: 15, sharpness: 40deg))
	((kind: "circle", pos: 0.5, fill: true),)

Default: (none, none)

mark-scale percent

Scale factor for marks or arrowheads.

Note that the default arrowheads scale automatically with double and triple strokes:



Default: 100%

extrude array

Draw a separate stroke for each extrusion offset to obtain a multi-stroke effect. Offsets may be numbers (specifying multiples of the stroke's thickness) or lengths.

Notice how the ends of the line need to shift a little depending on the mark. For basic arrow heads, this offset is computed with round-arrow-cap-offset().

Default: (0,)

crossing bool

If true, draws a backdrop of color crossing-fill to give the illusion of lines crossing each other.




You can also pass "crossing" as a positional argument as a shorthand for crossing: true.

Default: false

crossing-thickness number

Thickness of the "crossing" background stroke, if crossing: true, in multiples of the normal stroke's thickness. Defaults to the crossing-thickness option of diagram().



Default: auto

crossing-fill paint

Color to use behind connectors or labels to give the illusion of crossing over other objects. Defaults to the crossing-fill option of diagram().







Default: auto

dodge

Default: Opt

interpret-edge-args()

Interpret the positional arguments given to an edge()

Tries to intelligently distinguish the from, to, marks, and label arguments based on the types.

Generally, the following combinations are allowed:

```
edge(..<coords>, ..<marklabel>, ..<options>)
<coords> = (from, to) or (to) or ()
<marklabel> = (marks, label) or (label, marks) or (marks) or (label) or ()
<options> = any number of options specified as strings

Parameters
  interpret-edge-args(
    args,
    options
)
```

args

options

node()

Draw a labelled node in an diagram which can connect to edges.

Parameters

```
node(
  ..args,
  pos: point,
  label: content,
  inset: length auto,
  outset: length auto,
  shape: rect circle function auto,
  width,
  height,
  radius,
  stroke: stroke,
  fill: paint,
  corner-radius,
  defocus: number,
  extrude: array
)
```

..args

pos point

Dimensionless "elastic coordinates" (x, y) of the node. The coordinates are usually integers, but can be fractional.

See the <u>diagram()</u> options to control the physical scale of elastic coordinates.

Default: auto

label content

Content to display inside the node.

Default: auto

inset length or auto

Padding between the node's content and its bounding box or bounding circle. If auto, defaults to the node-inset option of diagram().

Default: auto

outset length or auto

Margin between the node's bounds to the anchor points for connecting edges.

This does not affect node layout, only how edges connect to the node.

Default: auto

shape rect or circle or function or auto

Shape to draw for the node. If auto, one of rect or circle is chosen depending on the aspect ratio of the node's label.

Some other shape functions are provided in the fletcher.shapes submodule, including diamond, pill, parallelogram, hexagon, and house.

Custom shapes should be specified as a function (node, extrude) => (..) returning cetz objects.

- The node argument is a dictionary containing the node's attributes, including its center position (node.real-pos), the label's dimensions (node.size), and other options (such as node.corner-radius, which may not have an effect for some shapes).
- The extrude argument is a length which the shape outline should be extruded outwards by. This serves two functions: to support automatic edge anchoring with a node outset, and to create multi-stroke effects using extrude.

Default: auto

width

Default: auto

height

Default: auto

radius

Default: auto

stroke stroke

Stroke style for the node outline. Defaults to the node-stroke option of diagram().

Default: auto

fill paint

Fill of the node. Defaults to the node-fill option of diagram().

Default: auto

corner-radius

Default: auto

defocus number

Strength of the "defocus" adjustment for connectors incident with this node. If auto, defaults to the node-defocus option of diagram().

Default: auto

extrude array


Draw strokes around the node at the given offsets to obtain a multi-stroke effect. Offsets may be numbers (specifying multiples of the stroke's thickness) or lengths.

The node's fill is drawn within the boundary defined by the first offset in the array.









See also the extrude option of edge().

Default: (0,)

compute-grid()

Determine the number, sizes and positions of rows and columns.

Parameters

```
compute-grid(
  nodes,
  options
)
```

nodes

options

expand-fractional-rects()

Convert an array of rects with fractional positions into rects with integral positions.

If a rect is centered at a factional position floor(x) < x < ceil(x), it will be replaced by two new rects centered at floor(x) and ceil(x). The total width of the original rect is split across the two new rects according two which one is closer. (E.g., if the original rect is at x = 0.25, the new rect at x = 0.

has 75% the original width and the rect at x = 1 has 25%.) The same splitting procedure is done for y positions and heights.

Parameters

```
rects array of rects
An array of rectangles of the form (pos: (x, y), size: (width, height)). The coordinates x and y may be floats.
```

Marks

interpret-mark()

Take a string or dictionary specifying a mark and return a dictionary, adding defaults for any necessary missing parameters.

Ensures all required parameters except rev and pos are present.

Parameters

```
interpret-mark(
  mark,
  defaults
)
```

mark

```
defaults

Default: (:)
```

interpret-marks-arg()

Parse and interpret the marks argument provided to edge(). Returns a dictionary of processed edge() arguments.

Parameters

```
interpret-marks-arg(arg: string array) -> dictiony
```

```
arg string or array
```

Can be a string, (e.g. "->", "<=>"), etc, or an array of marks. A mark can be a string (e.g., ">" or "head", "x" or "cross") or a dictionary containing the keys:

- kind (required) the mark name, e.g. "solid" or "bar"
- pos the position along the edge to place the mark, from 0 to 1
- rev whether to reverse the direction
- tail the visual length of the mark's tail
- parameters specific to the kind of mark, e.g., size or sharpness

round-arrow-cap-offset()

```
Calculate cap offset of round-style arrow cap, r \left( \sin \theta - \sqrt{1 - \left( \cos \theta - \frac{|y|}{r} \right)^2} \right).
```

Parameters

```
round-arrow-cap-offset(
  r: length,
    0: angle,
    y: length
)
```

r length

Radius of curvature of arrow cap.

θ angle

Angle made at the the arrow's vertex, from the central stroke line to the arrow's edge.

y length

Lateral offset from the central stroke line.

Utilities

get-arc-connecting-points()

Determine arc between two points with a given bend angle

The bend angle is the angle between chord of the arc (line connecting the points) and the tangent to the arc and the first point.

Returns a dictionary containing:

- center: the center of the arc's curvature
- radius
- start: the start angle of the arc

• stop: the end angle of the arc

Parameters

```
get-arc-connecting-points(
  from: point,
  to: point,
  angle: angle
) -> dictionary
```

from point

2D vector of initial point.

to point

2D vector of final point.

angle angle

The bend angle between chord of the arc (line connecting the points) and the tangent to the arc and the first point.





