SYSTEM SOFTWARE and COMPILERS18CS61

Prof. Sampada K S, Assistant Professor DEPT. OF CSE | RNSIT

Module-1

Introduction to System Software, Machine Architecture of SIC and SIC/XE. Assemblers: Basic assembler functions, machine dependent assembler features, machine independent assembler features, assembler design options. Basic Loader Functions

Text book 1: Chapter 1: 1.1,1.2,1.3.1,1.3.2, Chapter 2: 2.1 to 2.4, Chapter 3,3.1 RBT: L1, L2, L3

MACHINE ARCHITECTURE

19. About System software. Bring out the difference between System software and Application software

The Software is set of instructions or programs written to carry out certain task on digital computers. It is classified into system software and application software. System software consists of a variety of programs that support the operation of a computer. Application software focuses on an application or problem to be solved. System software consists of a variety of programs that support the operation of a computer.

Examples for system software are Operating system, compiler, assembler, macro processor, loader or linker, debugger, text editor, database management systems (some of them) and, software engineering tools. These software's make it possible for the user to focus on an application or other problem to be solved, without needing to know the details of how the machine works internally.

Difference between System Software and Application Software

System Software	Application Software
System Software intended to support the operation and use of computer	Application Software is primarily concerned with the solution of some problem using computer as a tool
Related to Machine Architecture	Not related to machine architecture
Machine Dependent	Machine Independent
Example: Compilers, Assemblers, OS etc	Example: Payroll System, Games etc

The Simplified Instructional Computer (SIC):

Simplified Instructional Computer (SIC) is a hypothetical computer that includes the hardware features most often found on real machines. There are two versions of SIC, they are, standard model (SIC), and, extension version (SIC/XE) (extra equipment or extra expensive).

SIC Machine Architecture:

We discuss here the SIC machine architecture with respect to its Memory and Registers, Data Formats, Instruction Formats, Addressing Modes, Instruction Set, Input and Output

- **Memory:** There are a total of 32,768(215)bytes in the computer memory. It uses Little Endian format to store the numbers, 3 consecutive bytes form a word, and each location in memory contains 8-bit bytes.
- •**Registers:** There are five registers, each 24 bits in length. Their mnemonic, number and use are given in the following table.

Mnemonic	Number	Use	
A	0	Accumulator; used for arithmetic operations	
X	1	Index register; used for addressing	
L	2	Linkage register; JSUB	
PC	8	Program counter	
SW	9	Status word, including CC	

- •Data Formats: Integers are stored as 24-bit binary numbers. 2's complement representation is used for negative values; characters are stored using their 8-bit ASCII codes. No floating-point hardware on the standard version of SIC.
- •Instruction Formats: All machine instructions on the standard version of SIC have the 24-bit format as shown above

2		
Opcode	X	Address

17. Generate the target address for the following machine instruction:
i) 032600H ii) 0310C303H iii)
03C300H iv) 003600H
if (B)= 006000, (Pc):003000, (X) =

Mode	Indication	Target address calculation Target
Direct	x = 0	TA = address
Indexed	x = 1	TA = address + (x)

There are two addressing modes available, which are as shown in the above table.

Parentheses are used to indicate the contents of a register or a memory location.

PROF. SAMPADA K S, CSE, RNSIT

•Addressing Modes:

3

•Instruction Set:

- 1. SIC provides, load and store instructions (LDA, LDX, STA, STX, etc.). Integer arithmetic operations: (ADD, SUB, MUL, DIV, etc.).
- 2. All arithmetic operations involve registers A and a word in memory, with the result being left in the register. Two instructions are provided for subroutine linkage.
- 3. COMP compares the value in register A with a word in memory, this instruction sets a condition code CC to indicate the result. There are conditional jump instructions: (JLT, JEQ, JGT), these instructions test the setting of CC and jump accordingly.
- 4. JSUB jumps to the subroutine placing the return address in register L, RSUB returns by jumping to the address contained in register L.

•Input and Output:

Input and Output are performed by transferring 1 byte at a time to or from the rightmost 8 bits of register A (accumulator). The Test Device (TD) instruction tests whether the addressed device is ready to send or receive a byte of data. Read Data (RD), Write Data (WD) are used for reading or writing the data.

Data movement and Storage Definition

LDA, STA, LDL, STL, LDX, STX (A- Accumulator, L – Linkage Register, X – Index Register), all uses3-byte word. LDCH, STCH associated with characters uses 1-byte. There are no memory-memory move instructions.

Storage definitions are

- WORD ONE-WORD CONSTANT
- RESW ONE-WORD VARIABLE
- BYTE ONE-BYTE CONSTANT
- RESB ONE-BYTE VARIABLE

Example Programs (SIC):

Example 1: Simple data and character movement operation

To store the value 5 in a variable ALPHA and character Z in a variable C1

LDA FIVE

STA ALPHA

	LDCH	CHARZ
	STCH	C1
ALPHA	RESW	1
FIVE	WORD	5
CHARZ	BYTE	C'Z'
C1	RESB	1

Example 2: Arithmetic operations: BETA=ALPHA+INCR+1

```
LDA
                   ALPHA
      ADD
                   INCR
      SUB
                   ONE
      STA
                   BETA
. . . . . . . .
```

.

ONE WORD 1 ALPHA **RESW** 1 **BEETA RESW** 1 **INCR** RESW 1

Example 3: Looping and Indexing operation

To perform STR2=STR1 where STR1 is a string of 11 characters.

LDX ZERO X = 0

LDCH STR1, X LOAD A FROM STR1 **MOVECH** STCH STR2, X STORE A TO STR2 **ELEVEN** ADD 1 TO X, TEST TIX

JLT **MOVECH**

PROF. SAMPADA K S, CSE, RNSIT

STR1 BYTE C 'HELLO WORLD'

STR2 RESB 11 ZERO WORD 0 ELEVEN WORD 11

Example 4: Input and Output operation

To read a character from the input device and to write a character to the output device.

INLOOP TD INDEV : TEST INPUT DEVICE

JEQ INLOOP : LOOP UNTIL DEVICE IS READY

RD INDEV : READ ONE BYTE INTO A

STCH DATA : STORE A TO DATA

•

OUTLOOP TD OUTDEV : TEST OUTPUT DEVICE

JEQ OUTLP : LOOP UNTIL DEVICE IS READY

LDCH DATA : LOAD DATA INTO A

WD OUTDEV : WRITE A TO OUTPUT DEVICE

•

INDEV BYTE X 'F5': INPUT DEVICE NUMBER OUTDEV BYTE X '08': OUTPUT DEVICE NUMBER

Example 5: To transfer two hundred bytes of data from input device to memory

LDX ZERO

CLOOP TD INDEV

JEQ CLOOP

RD INDEV STCH RECORD, X

TIX B200 JLT CLOOP

.

INDEV BYTE X 'F5'
RECORD RESB 200
ZERO WORD 0
B200 WORD 200

20. About instruction format and addressing modes of SIC/XE architecture with examples.

- SIC/XE Machine Architecture: SIC/XE architectur
- **Registers** : Additional B, S, T, and F registers are provided by SIC/XE, in addition to the registers of SIC.

• **Memory**: Maximum memory available on a SIC/XE system is 1 Megabyte (220 bytes).

Mnemonic	Number	Special use
В	3	Base register
S	4	General working register
Т	5	General working register
F	6	Floating-point accumulator (48 bits)

• Data Formats: There is a 48-bit floating-point data type, F*2^(e-1024)

1	11	36				
s	exponent	fraction				

- **Instruction Formats**: The new set of instruction formats fro SIC/XE machine architecture are as follows.
- Format 1 (1 byte): contains only operation code (straight from table).

• Format 2 (2 bytes): first eight bits for operation code, next four for register 1 and following four for register 2. The numbers for the registers go according to the numbers indicated at the registers section (ie, register T is replaced by hex 5, F is replaced by hex 6).

8	4	4
op	r1	r2

• Format 3 (3 bytes): First 6 bits contain operation code, next 6 bits contain flags, last 12 bits contain displacement for the address of the operand. Operation code uses only 6 bits, thus the second hex digit will be affected by the values of the first two flags (n and i). The flags, in order, are: n, i, x, b, p, and e. Its functionality is explained in the next section. The last flag e indicates the instruction format (0 for 3 and 1 for 4).

6	1	1	1	1	1	1	12
ор	n	į	x	ь	P	e	disp

• Format 4 (4 bytes): same as format 3 with an extra 2 hex digits (8 bits) for addresses that require more than 12 bits to be represented.

6	1	1	1	1	1	1	20
op	n	į	X	b	p	e	address

Addressing modes & Flag Bits

Five possible addressing modes plus the combinations are as follows.

- **1. Direct** (x, b, and p all set to 0): operand address goes as it is. n and i are both set to the same value, either 0 or 1. While in general that value is 1, if set to 0 for format 3 we can assume that the rest of the flags (x, b, p, and e) are used as a part of the address of the operand, to make the format compatible to the SIC format.
- **2. Relative** (either b or p equal to 1 and the other one to 0): the address of the operand should be added to the current value stored at the B register (if b = 1) or to the value stored at the PC register (if p = 1)
- **3. Immediate**(i = 1, n = 0): The operand value is already enclosed on the instruction (ie. lies on the last 12/20 bits of the instruction)
- **4. Indirect**(i = 0, n = 1): The operand value points to an address that holds the address for the operand value.
- **5. Indexed** (x = 1): value to be added to the value stored at the register x to obtain real address of the operand. This can be combined with any of the previous modes except immediate.

The various flag bits used in the above formats have the following meanings e -> e = 0 means format 3, e = 1 means format 4.

Instruction Set:

SIC/XE provides all of the instructions that are available on the standard version. In addition we have, Instructions to load and store the new registers LDB, STB, etc, Floating- point arithmetic operations, ADDF, SUBF, MULF, DIVF, Register move instruction: RMO

Register-to-register arithmetic operations, ADDR, SUBR, MULR, DIVR and, Supervisor call instruction : SVC.

•Input and Output:

There are I/O channels that can be used to perform input and output while the CPU is executing other instructions. Allows overlap of computing and I/O, resulting in more efficient system

operation. The instructions SIO, TIO, and HIO are used to start, test and halt the operation of I/O channels.

Example Programs (SIC/XE)

Example 1: Simple data and character movement operation

To store the value 5 in a variable ALPHA and character Z in a variable C1

LDA #5

STA ALPHA

LDA #90

STCH C1

•

.

ALPHA RESW 1

C1 RESB 1

Example 2: Arithmetic operations

BETA=ALPHA+INCR+1

LDS INCR

LDA ALPHA

ADDR S,A

SUB 1

STA BETA

.

.

ALPHA RESW 1

INCR RESW 1

BETA RESW 1

Example 3: Looping and Indexing operation

To perform STR2=STR1 where STR1 is a string of 11 characters.

LDT #11

LDX #0

MOVECH LDCH STR1, X : LOAD A FROM STR1

STCH STR2, X : STORE A TO STR2

TIXR T : ADD 1 TO X, TEST (T)

JLT MOVECH

.....

STR1 BYTE C 'HELLO WORLD'

STR2 RESB 11


Difference between SIC and SIC/XE

	SIC	SIC/XE
Memory	2 ¹⁵ bytes	2 ²⁰ bytes
Registers	5 (A,X,L,PC & SW)	9(A,X,L,B,S,T,F,PC & SW)
Data Formats	No Floating Point Hardware	Supports Floating Point Hardware
Instruction Format	One	Four
Addressing Mode	Two	Five and its combination

ASSEMBLERS

The basic assembler functions are:

- Translating mnemonic language code to its equivalent object code.
- Assigning machine addresses to symbolic labels.



SIC Assembler Directive:

- START: Specify name and starting address for the program
- END: Indicate End of the program and (optionally) specify the first execution instruction in the program.
- BYTE: Generate character or hexadecimal constant, occupying as many bytes as needed to represent the constant.
- WORD: Generate one-word integer constant.
- RESB: Reserve the indicated number of bytes for a data area.
- RESW: Reserve the indicated number of words for a data area.

A simple SIC Assembler

The design of assembler in other words:

- 1. Convert mnemonic operation codes to their machine language equivalents.
 - Example: Translate LDA to 00.
- 2. Convert symbolic operands to their equivalent machine addresses.
 - Example: Translate GAMMA to 400F
- 3. Build the machine instructions in the proper format.
- 4. Convert the data constants to internal machine representations.
- Example: ONE WORD 1 is translated to **000001**
- 5. Write the object program and the assembly listing

Two Pass Assembler

16. About the PASS-1 of two pass assembler and explain with an example.

Pass-1

- Assign addresses to all the statements in the program
- Save the addresses assigned to all labels to be used in *Pass-2*
- Perform some processing of assembler directives such as RESW, RESB to find the length of data areas for assigning the address values.
- Defines the symbols in the symbol table(generate the symbol table)

Pass-2

- Assemble the instructions (translating operation codes and looking up addresses).
- Generate data values defined by BYTE, WORD etc.
- Perform the processing of the assembler directives not done during pass-1.
- Write the object program and assembler listing.

Assembler Design:

The most important things which need to be concentrated is the generation of Symbol table and resolving *forward references*.

- Symbol Table:
 - This is created during pass 1
 - All the labels of the instructions are symbols
 - Table has entry for symbol name, address value.
- Forward reference:
 - Symbols that are defined in the later part of the program are called forward referencing.
 - There will not be any address value for such symbols in the symbol table in pass 1.

Figure 2.1: Assembly Language Program with object code Object Code for Instruction

DELTA=GAMMA + INCR - 1

LOCCTR	S	OURCE STATI	OBJECT CODE	
	ARTH	START	4000	
4000		LDA	GAMMA	00400F
4003		ADD	INCR	184012
4006		SUB	ONE	1C4015
4009		STA	DELTA	0C400C
400C	DELTA	RESW	1	
400F	GAMMA	RESW	1	
4012	INCR	RESW	1	
4015	ONE	WORD	1	000001
4018		END		

OPTAB							
MNEMONIC	OPCODE						
LDA	00						
ADD	18						
SUB	1C						
STA	0C						

SYMTAB						
LABEL	ADDRESS					
DELTA	400C					
GAMMA	400F					
INCR	4012					
ONE	4015					

LDA GAMMA

Opcode	X	Addre	ess			
0000 0000	0	100	0000	0000	1111	
0 0		4	0	0	F	

12. About thea) Header recordb)Text recordc)End recordd)Modification record

OBJECT PROGRAM

- The simple object program contains three types of records: Header record, Text record and end record.
- o The header record contains the starting address and length.
- o Text record contains the translated instructions and data of the program, together with an indication of the addresses where these are to be loaded.
- The end record marks the end of the object program and specifies the address where the execution is to begin.

Syntax

- Header record
 - Col. 1 H

- Col. 2~7 Program name
- Col. 8~13 Starting address of object program (hex)
- Col. 14~19 Length of object program in bytes (hex)
- · Text record
 - Col. 1 T
 - Col. 2~7 Starting address for object code in this record (hex)
 - Col. 8~9 Length of object code in this record in bytes (hex)
 - Col. 10~69 Object code, represented in hex (2 col. per byte)
- End record
 - Col.1 E
 - Col.2~7 Address of first executable instruction in object program (hex)

HARTH 00400000018 T0040000C00400F1840121C40150C400C T00401503000001

E004000

Fig 2.2 Object program corresponding to Fig 2.1

Write the object program for the ALP given below

STR2 = STR1 where STR1="HELLO"

LOCC TR	S	OURCE STA	TEMENT	OBJECT CODE
	COPY	START	2000	
2000		LDX	ZERO	042019
2003	MOVECH	LDCH	STR1,X	50A00F
2006		STCH	STR2,X	54A014
2009		TIX	FIVE	2C201C
200C		JLT	MOVECH	382003
200F	STR1	BYTE	C'HELLO'	48454C4C4F
2014	STR2	RESB	5	
2019	ZERO	WORD	0	000000
201C	FIVE	WORD	5	000005
20 <mark>1F</mark>		END		

OPTAB						
MNEMONIC	OPCODE					
LDX	04					
LDCH	50					
STCH	54					
TIX	2C					
JLT	38					

SYMTAB	
LABEL	ADDRESS
MOVECH	2003
STR1	200F
STR2	2014
ZERO	2019
FIVE	201C

Object Code for the instruction

LDCH STR1,X

Opcode	X	Address
0101 0000	1	010 0000 0000 1111
5 0		A 0 0 F

HCOPY 00200000001F T0020001404201950A00F54A0142C201C38200348454C4C4F T0020190600000000005

E0020000

Algorithms and Data structure

The simple assembler uses two major internal data structures: the operation Code Table (OPTAB) and the Symbol Table (SYMTAB).

OPTAB:

- It is used to lookup mnemonic operation codes and translates them to their machine language equivalents. In more complex assemblers the table also contains information about instruction format and length.
- In pass 1 the OPTAB is used to look up and validate the operation code in the source program. In pass 2, it is used to translate the operation codes to machine language. In simple SIC machine this process can be performed in either in pass 1 or in pass 2. But for machine like SIC/XE that has instructions of different lengths, we must search OPTAB in the first pass to find the instruction length for incrementing LOCCTR.

- In pass 2 we take the information from OPTAB to tell us which instruction format to use in assembling the instruction, and any peculiarities of the object code instruction.
- OPTAB is usually organized as a hash table, with mnemonic operation code as the
 key. The hash table organization is particularly appropriate, since it provides fast
 retrieval with a minimum of searching. Most of the cases the OPTAB is a static
 table- that is, entries are not normally added to or deleted from it. In such cases it is
 possible to design a special hashing function or other data structure to give optimum
 performance for the particular set of keys being stored.

SYMTAB:

- This table includes the name and value for each label in the source program, together with flags to indicate the error conditions (e.g., if a symbol is defined in two different places).
- During Pass 1: labels are entered into the symbol table along with their assigned address value as they are encountered. All the symbols address value should get resolved at the pass 1.
- During Pass 2: Symbols used as operands are looked up the symbol table to obtain the address value to be inserted in the assembled instructions.
- SYMTAB is usually organized as a hash table for efficiency of insertion and retrieval. Since entries are rarely deleted, efficiency of deletion is the important criteria for optimization.
- Both pass 1 and pass 2 require reading the source program. Apart from this an intermediate file is created by pass 1 that contains each source statement together with its assigned address, error indicators, etc. This file is one of the inputs to the pass 2.
- A copy of the source program is also an input to the pass 2, which is used to retain the operations that may be performed during pass 1 (such as scanning the operation field for symbols and addressing flags), so that these need not be performed during pass 2. Similarly, pointers into OPTAB and SYMTAB is retained for each operation code and symbol used. This avoids need to repeat many of the table-searching operations.

LOCCTR:

LOCCTR is an important variable which helps in the assignment of the addresses. LOCCTR is initialized to the beginning address mentioned in the START statement of the program. After each statement is processed, the length of the assembled instruction is added to the LOCCTR to make it point to the next instruction. Whenever a label is encountered in an instruction the LOCCTR value gives the address to be associated with that label.

The Algorithm for Pass 1:

```
begin
 read first input line
 if OPCODE = 'START' then begin
            save #[Operand] as starting address
            initialize LOCCTR to starting address
            write line to intermediate file
            read next input line
    end(if START)
  else
     initialize LOCCTR to 0
     While OPCODE != END' do
      begin
         if this is not a comment line then
              if there is a symbol in the LABEL field then
                 begin
                   search SYMTAB for LABEL
                  if found then
                    set error flag (duplicate symbol)
                  else
                    insert(LABEL,LOCCTR) into SYMTAB
             end(if symbol)
             search OPTAB for OPCODE
               if found then
                   add 3 (instruction length) to LOCCTR
               else if OPCODE = 'WORD' then
                    add 3 to LOCCTR
                else if OPCODE = 'RESW' then
                    add 3 * #[OPERAND] to LOCCTR
               else if OPCODE = 'RESB' then
                    add #[OPERAND] to LOCCTR
               else if OPCODE = 'BYTE' then
                    begin
                        find length of constant in bytes
                        add length to LOCCTR
                    end(if BYTE)
                 else
                    set error flag (invalid operation code)
             end (if not a comment)
                 write line to intermediate file
                 read next input line
            end { while not END}
         write last line to intermediate file
         Save (LOCCTR - starting address) as program length
     End {pass 1}
```

- The algorithm scans the first statement START and saves the operand field (the address) as the starting address of the program. Initializes the LOCCTR value to this address. This line is written to the intermediate line.
- If no operand is mentioned the LOCCTR is initialized to zero. If a label is encountered, the symbol has to be entered in the symbol table along with its associated address value.
- If the symbol already exists that indicates an entry of the same symbol already exists. So an error flag is set indicating a duplication of the symbol.
- It next checks for the mnemonic code, it searches for this code in the OPTAB. If found then the length of the instruction is added to the LOCCTR to make it point to the next instruction.
- If the opcode is the directive WORD it adds a value 3 to the LOCCTR. If it is RESW, it needs to add the number of data word to the LOCCTR. If it is BYTE it adds a value one to the LOCCTR, if RESB it adds number of bytes.
- If it is END directive then it is the end of the program it finds the length of the program by evaluating current LOCCTR the starting address mentioned in the operand field of the END directive. Each processed line is written to the intermediate file.

The Algorithm for Pass 2:

```
Begin
 read 1st input line
   if OPCODE = 'START' then
      write listing line
       read next input line
 end
write Header record to object program
initialize 1st Text record
 while OPCODE != 'END' do
   begin
      if this is not comment line then
        begin
           search OPTAB for OPCODE
           if found then
           begin
               if there is a symbol in OPERAND field then begin
                      search SYMTAB for OPERAND
                      if found then
                      store symbol value as operand address
                   else
```

```
begin
                                   store 0 as operand address
                                           set error flag (undefined symbol)
                                  end
                             end (if symbol)
                            else
                                store 0 as operand address
                                 assemble the object code instruction
                   end(if opcode found)
              else if OPCODE = 'BYTE' or 'WORD" then
                  convert constant to object code
            if object code doesn't fit into current Text record then
              begin
                    Write text record to object program
                     initialize new Text record
               end
           add object code to Text record
         end {if not comment}
              write listing line
              read next input line
      end {while not END}
           write last text record to object program
           write End record to object program
           write; ast listing linbe
End {Pass 2}
```

Here the first input line is read from the intermediate file. If the opcode is START, then this line is directly written to the list file. A header record is written in the object program which gives the starting address and the length of the program (which is calculated during pass 1). Then the first text record is initialized. Comment lines are ignored. In the instruction, for the opcode the OPTAB is searched to find the object code.

If a symbol is there in the operand field, the symbol table is searched to get the address value for this which gets added to the object code of the opcode. If the address not found then zero value is stored as operands address. An error flag is set indicating it as undefined. If symbol itself is not found then store 0 as operand address and the object code instruction is assembled.

If the opcode is BYTE or WORD, then the constant value is converted to its equivalent object code (for example, for character EOF, its equivalent hexadecimal value '454f46' is stored). If the object code cannot fit into the current text record, a new text record is created and the rest of the instructions object code is listed. The text records are written to the object program. Once the whole program is assembled and when the END directive is encountered, the End record is written.

Generate the complete object program for the following assembly level program

T O C CITIE		COLIDOROGIA		
LOCCTR		SOURCE STAT	TEMENT	OBJECT CODE
	SUM	START	0	
0000	FIRST	CLEAR	X	B410
0002		LDA	#0	010000
0005		+LDB	#TOTAL	69101788
		BASE	TOTAL	
0009	LOOP	ADD	TABLE,X	1BA00C
000C		TIX	COUNT	2F2006
000F		JLT	LOOP	3B2FF7
0012		STA	TOTAL	0F4000
0015	COUNT	RESW	1	
0018	TABLE	RESW	2000	
1788	TOTAL	RESW	1	
178B		END	FIRST	

Program Length= LOCCTR - STARTING ADDRESS=178B-0=178BH

OPTAB							
MNEMONIC	OPCODE						
LDA	00						
LDB	68						
ADD	18						
TIX	2C						
JLT	38						
STA	0C						
CLEAR	B4						

SYMTAB						
LABEL	ADDRESS					
FIRST	0000					
LOOP	0009					
COUNT	0015					
TABLE	0018					
TOTAL	1788					

21. Define code for the SUM		wing \$		E soui			e objec 1.	t
FIRST	LDA		DX ZER(ERO		
LOOP	TIX	ADD		TABL	_E,X			
		JLT STA RSL		111	LOC TO			
TABLE COUNT ZERO TOTAL		R R WO	ESW ESW		20 1 0 1	000		
Mnemonic Opcode	END LDA 00		FIRS STA 0C		TIX 2C	JLT 38	RSUI 4C	3

The Object code for the instruction

+LDB #TOTAL

Opcode	N	1	X	В	Р	Е	Address				
0110 10	0	1	0	0	0	1	0000 0001 0111 1000 1000				
6	9				1		0	1	7	8	8

STA TOTAL

Opcode	N	1	Х	В	Р	Е	Displ	acem	ent
0000 11	1	1	0	1	0	0	0000	0000	0000
0	F			4			0	0	0

The instruction cannot be assembled by using Program Counter Relative Addressing Mode because the Displacement what we calculate can not fit into 12 bit displacement. So, Base Relative addressing mode is used.

Displacement =
$$TA - (B)$$

= $1788-1788=0$

Object Program

HSUM 0000000178B

T00000015B410010000691017881BA00C2F20063B2FF70F4000

E000000

Machine dependent Assembler Features

- Machine Dependent Assembler Features
 - Instruction formats and addressing modes (SIC/XE)
 - Program relocation

SIC/XE Instruction Formats and Addressing Modes

• PC-relative or Base-relative (BASE directive needs to be used) addressing: **op m**

Indirect addressing: op @m
Immediate addressing: op #c
Extended format (4 bytes): +op m
Index addressing: op m,X

Addressing modes

- Register as 1st operand
 - = 2 bytes
- 2 operand registers
 - = 2 bytes

Symbol as the operand

- = 3 bytes
- RSUB has length
 - = 3 bytes
- Preceding with +
 - = 4 bytes

- Program Counter Relative Addressing Disp=TA-PC
- Base Relative Addressing Disp=TA-(base register)
- Immediate Addressing
 - LDA #4095
- Indirect Addressing +LDA @ALPHA ,X
- Register Addressing
 Uses instruction format 2.
 CLEAR A { 1 OPERAND REGISTER}
 COMPR A,S { 2 OPERAND REGISTER}
- Direct Addressing
 - +LDA ALPHA
 - +LDB #4096

Addressing


- Program-Counter relative addressing (Format 3)
 - -2048 ≤ Displacement ≤ +2047
- Base relative addressing (Format 3)
 - > 0 ≤ Displacement ≤ 4095
- Extended instruction format (Format 4)
 - 20-bit address field, which is large enough to contain the full memory address.
 - Using the prefix +

Example 1: PC Relative Addressing

Line	Loc	Source statement			Object code
10	0000	FIRST	STL	RETADR	17202D

Hex	Binary				
	op nixbpe	disp/address			
17202D	$0\ 0\ 0\ 1\ 0\ 1\ 1\ 1\ 0\ 0\ 1\ 0\ 0\ 0\ 0\ 0\ 0\ 1$	01101			

Example 2: PC Relative Addressing



Hex	Binary				
	op nixbpe disp/address				
3F2FEC	001111100101111111101100				

Base Relative Addressing

Difference between PC-relative and Base-relative addressing

- The assembler knows what the contents of the Program Counter will be at execution time. Base register?
- The base register is under control of the programmer. Therefore, the programmer must tell the assembler what the base register will contain during execution of the program

Assembler Directives

BASE	Informs the assembler that the base register will contain the address of #[Operand]
NOBASE	Informs the assembler that the contents of the base register can no longer be relied upon for addressing

Example: Base Relative Addressing

Line	Loc	Source statement	Object code
160	104E	STCH BUFFER, X	57C003

Hex	Binary				
	op nixbpe disp/address				
57C003	01010111110000000000011				

Program Relocation

Sometimes it is required to load and run several programs at the same time. The system must be able to load these programs wherever there is place in the memory. Therefore the exact starting is not known until the load time.




Fig: Examples of Program Relocation

The above diagram shows the concept of relocation. Initially the program is loaded at location 0000. The instruction JSUB is loaded at location 0006.

- The address field of this instruction contains 01036, which is the address of the instruction labeled RDREC. The second figure shows that if the program is to be loaded at new location 5000.
- The address of the instruction JSUB gets modified to new location 6036. Likewise
 the third figure shows that if the program is relocated at location 7420, the JSUB
 instruction would need to be changed to 4B108456 that correspond to the new
 address of RDREC.
- The only part of the program that require modification at load time are those that specify direct addresses. The rest of the instructions need not be modified. The instructions which doesn't require modification are the ones that is not a memory address (immediate addressing) and PC-relative, Base-relative instructions.
- From the object program, it is not possible to distinguish the address and constant The
 assembler must keep some information to tell the loader. The object program that
 contains the modification record is called a relocatable program.
- For an address label, its address is assigned relative to the start of the program

(START 0). The assembler produces a *Modification record* to store the starting location and the length of the address field to be modified. The command for the loader must also be a part of the object program. The Modification has the following format:

Modification record

- Col. 1 M
- Col. 2-7 Starting location of the address field to be modified, relative to the beginning of the program (Hex)
- Col. 8-9 Length of the address field to be modified, in half-bytes (Hex)

Object Program Format

	Column	Contents			
	1	Н			
Header	2-7	Program name			
Record	8-13	Starting address of object program (HEX)			
	14-19	Length of object program in bytes (HEX)			
	1	Т			
Text	2-7	Starting address for object code in this record (HEX)			
Record 8-9		Length of object code in this record in bytes (HEX)			
	10-69	Object code (HEX, 2 columns per byte of object code)			
	1	M			
Mod. Record	2-7	Starting location of the address field to be modified, relative to the beginning of the program (HEX)			
record	8-9	Length of the address field to be modified, in half-bytes (HEX)			
End	1	E			
Record	2-7	Address of first executable instruction (HEX)			

One modification record is created for each address to be modified. The length is stored in half-bytes (4 bits). The starting location is the location of the byte containing the leftmost bits of the address field to be modified. If the field contains an odd number of half-bytes, the starting location begins in the middle of the first byte.

Design and Implementation Issues:

Some of the features in the program depend on the architecture of the machine. If the program is for SIC machine, then we have only limited instruction formats and hence limited addressing modes. We have only single operand instructions. The operand is always a memory reference. Anything to be fetched from memory requires more time. Hence the improved version of SIC/XE machine provides more instruction formats and hence more addressing modes. The moment we change the machine architecture the availability of number of instruction formats and the addressing modes changes. Therefore the design usually requires considering two things: Machine-dependent features and Machine-independent features.

2.3 Machine-Independent Assembler Features

- 2.3.1 Literals
- 2.3.2 Symbol-Defining Statements
- 2.3.3 Expressions
- 2.3.4 Program Blocks
- 2.3.5 Control Sections and Program Linking

LITERALS:

- It is often convenient for the programmer to be able to write the value of a constant operand as a part of the instruction that uses it.
- This avoids having to define the constant elsewhere in the program and make up a label for it.
- Such an operand is called a literal because the value is stated "literally" in the instruction.
- In SIC/XE assembler language notation, a literal is identified with the prefix =, which is followed by a specification of the literal value, using the same notation as in the BYTE statement.

- The difference between a literal and an immediate operand.
 - (#) Immediate addressing: the operand value is assembled as part of the machine instruction.
 - (=) Literal addressing: the assembler generates the specified value as a constant at some other memory location.

40 45 50 55 60 65 70 93	0017 001A 001D 0020 0023 0026 002A	ENDFIL	J LDA STA LDA STA +JSUB J LTORG	CLOOP =C'EOF' BUFFER #3 LENGTH WRREC GRETADR	3F2FEC 032010 0F2016 010003 0F200D 4B10105D 3E2003
95	002D 0030	* RETADR	=C'EOF' RESW	1	454F46

- All of the literal operands used in a program are gathered together into one or more literal pools. Normally literals are placed into a pool at the end of the program.
- When the assembler encounters a LTORG statement, it creates a literal operands used since the previous LTORG (or the beginning of the program).
- Most assemblers recognize duplicate literals and store only one copy of the specified data value.
 - By comparison of the character strings defining them.
 - > EX: the literal =X'05' (Figure 2.9, Line 215 and 230)
 - EX: =C'EOF' and =X'454F45' ?

The implementation of literals

- The basic data structure needed is a literal table (LITTAB).
 - Literal name, value, length, and address

Pass1:

- > Search and update LITTAB for the specified literal name
- When encounters a LTORG statement or the end of the program, the assembler makes a scan of the LITTAB and assigns an address for all unallocated literals
- Update the location counter to reflect the number of bytes occupied by each literal

Pass2:

- Search LITTAB for the address of each literal encountered
- Literal values placed at correct locations in the object program
- ➤ If a literal value represents an address in the program, the assembler must also generate the appropriate Modification record.

SYMBOL DEFINING STATEMENTS:

18. About symbol definition statements


EQU assembler directive

- **EQU** (for "equate") assembler directive allows the programmer to define symbols and specify their values.
 - Improve readability in place of numeric values
 - EX: "MAXLEN" and " * " (Figure 2.9, Line 106 and 107)

93			LTORG			
ı	002D	*	=C'EOF'			454F46
95	0030	RETADR	RESW	1		
100	0033	LENGTH	RESW	1		
105	0036	BUFFER	RESB	4096		
106	1036	BUFEND	EQU	*		
107	1000	MAXLEN	EQU	BUFEND-BUF	FER	
110						
115			SUBROU'I	TINE TO READ	RECORD	INTO BUFFER
120						
125	1036	RDREC	CLEAR	X		B410
130	1038		CLEAR	A		B400
132	103A		CLEAR	S		B440
133	103C		+LDT	#MAXLEN		75101000
135	1040	RLOOP	TD	INPUT		E32019


EQU assembler directive

- The resulting object code is exactly the same as in the original version of the instruction; however, the source statement is easier to understand.
- Another common use of EQU is in defining mnemonic names for registers.




ORG assembler directive


- ORG (for "origin") assembler directive
 - When ORG is encountered during assembly of a program, the assembler resets its location counter (LOCCTR) to the specified value.
- Example:
 - > SYMBOL is 6-byte, VALUE is 1-word, and FLAGS is 2-byte



Use EQU assembler directives



Use ORG assembler directives



Restrictions


EQU:

all symbols used on the right-hand side of the statement must have been defined previously in the program.




ORG:

all symbols used to specify the new location counter value must have been previously defined.



Expressions

- Assemblers generally allow arithmetic expressions formed according to the normal rules using the operators +, -, *, /.
- Division is usually defined to produce an integer result.
- Individual terms in the expression may be constants, userdefined symbols, or special terms.
- " * " : This special term represents the value of the next unassigned memory location.



- Expression Terms
 - > Relative terms: defined relative to the beginning of the program
 - Absolute terms: independent of program location

Absolute and Relative Expressions

- Absolute Expressions
 - Contains only absolute terms
 - Contains relative terms provided the relative terms occur in pairs with opposite signs; the dependency on the program starting address is canceled out; the result is an absolute value

107 MAXLEN EQU BUFEND-BUFFER

- Relative Expressions
 - Contains an odd number of relative terms, with one more positive terms than negative terms
 - No relative term may enter into a multiplication or division operation

Defining Symbol Types in the Symbol Table

- To determine the type of an expression, we must keep track of the types of all symbols defined in the program.
- For this purpose we need a flag in the symbol table to indicate type of value (absolute or relative) in addition to the value itself.

Symbol	Туре	Value
RETADR	R	0030
BUFFER	R	0036
BUFEND	R	1036
MAXLEN	A	1000

With this information the assembler can easily determine the type of each expression used as an operand and generate Modification records in the object program for relative values.

Program Blocks vs. Control Sections


Program Blocks

Refer to segments of code that are rearranged within a single object program unit

Control Sections

Refer to segments that are translated into independent object program units

Program blocks:



- The source programs logically contained subroutines, data areas, etc. However, they were handled by the assembler as one entity, resulting in a single block of object code.
- Many assemblers provide features that allow more flexible handling of the source and object programs.
 - Some features allow the generated machine instructions and data to appear in the object program in a different order from the corresponding source statements.
 - Other features result in the creation of several independent parts of the object program.
 - These parts maintain their identity and are handled separately by the loader.
- The assembler directive USE indicates which portions of the source program belong to the various blocks.
- Each program block may actually contain several separate segments of the source program. The assembler will (logically) rearrange these segments to gather together the pieces of each block.

Assembler Directives

- <symbol> CSECT
 - The CSECT assembler directive signals the start of a new control section named <symbol>
- EXTDEF < symbol₁, symbol₂, ... symbol_n >
 - The EXTDEF (external definition) statement in a control section names symbols, called external symbols, that are defined in this control section and may be used by other sections.
 - Control section names do not need to be named in an EXTDEF statement because they are automatically considered to be external symbols.
- EXTREF < symbol₁, symbol₂, ... symbol_n >
 - The EXTREF (external reference) statement names symbols that are used in this control section and are defined elsewhere.

Assembler Design options:

One-Pass Assemblers

- The main problem in trying to assemble a program in one pass involves forward references.
- Eliminate forward references
 - > Data items are defined before they are referenced.
 - But, forward references to labels on instructions cannot be eliminated as easily.
 - Prohibit forward references to data items.
- There are two main types of one-pass assembler.
 - Load-and-Go: Produces object code directly in memory for immediate execution
 - Object Program Output: Produces the usual kind of object program for late execution.

Load-and-Go Assemblers (1/2)

- This kind of load-and-go assembler is useful in a system that is oriented toward program development and testing.
- If an instruction operand is a symbol that has not yet been defined, the operand address is omitted when the instruction is assembled.
 - The symbol used as an operand is entered into the symbol table.
 - This entry is flagged to indicate that the symbol is undefined.
 - The address of the operand field of the instruction that refers to the undefined symbol is added to a list of forward references associated with the symbol table entry.
 - When the definition for a symbol is encountered, the forward reference list for that symbol is scanned, and the proper address is inserted into any instructions previously generated.
 - At the end of the program, all symbols must be defined without any * in SYMTAB.
 - For a load-and-go assembler, the actual address must be known at assembly time.

Object Program Output Assemblers

- One-pass assemblers that produce object programs as output are often used on systems where external workingstorage devices are not available.
- The assembler generate another Text record with the correct operand address.
- When the program is loaded, this address will be inserted into the instruction by the action of the loader.
- The object program records must be kept in their original order when they are presented to the loader.

14. About multi pass assembler. Multi-Pass Assemblers

- In our discussion of the EQU assembler directive, we required that any symbol used on the RHS be defined previously in the source program.
- Consider, for example, the sequence

ALPHA	EQU	BETA
BETA	EQU	DELTA
DELTA	RESW	1

Two-pass assemblers

Multi-Pass Assemblers

- The general solution is a multi-pass assembler that can make as many passes as are needed to process the definitions of symbols.
- It is not necessary for such an assembler to make more than two passes over the entire program.
- The method we describe involves storing those symbol definitions that involve forward references in the symbol table.
 - ➤ This table also indicates which symbols are dependent on the values of others, to facilitate symbol evaluation.
- Explain how multi-pass assembler handles the following forward reference
- HALFSZ EQU MAXLEN/2
- 2 MAXLEN EQU BUFEND-BU 3 PREVBT EQU BUFFER-1 **BUFEND-BUFFER**
- 4 BUFFER RESB 4096
- 5 BUFEND EQU

Assume that the starting address of first instruction is 1000H

LOADERS

Introduction 9. About Control Sections and Program Linking

The Source Program written in assembly language or high level language will be translated to object program, which is in the machine language form for execution. This translation is either from assembler or from compiler, contains translated instructions and data values from the source program, or specifies addresses in primary memory where these items are to be loaded for execution.

15. About program relocation

This contains the following three processes, and they are,

- □ **Loading** which allocates memory location and brings the object program into memory for execution-(Loader)
- □ **Linking**-which combines two or more separate object programs and supplies the information needed to allow references between them -(Linker)
- □ **Relocation**-which modifies the object program so that it can be loaded at an address different from the location originally specified-(Linking Loader)

Basic Loader Functions:

A loader is a system program that performs the loading function. It brings object program into memory and starts its execution. The role of loader is as shown in the figure 4.1. The assembler generates the object program and later loaded to the memory by the loader for execution.




Figure 4: The Role of Loader

The different types of loaders are

- Absolute loader
- Bootstrap loader
- Relocating loader (relative loader) and
- Direct linking loader

1. Absolute Loader

13. About an Absolute Loader

The operation of absolute loader is very simple. The object code is loaded to specified locations in the memory. At the end the loader jumps to the specified address to begin execution of the loaded program. The role of absolute loader is as shown in the figure.

The advantage of absolute loader is simple and efficient. But the disadvantages are, the need for programmer to specify the actual address, and, difficult to use subroutine libraries.




Figure 4.4: The Role of Absolute Loader

The algorithm for this type of loader is given here. The object program and, the object program loaded into memory by the absolute loader are also shown. Each byte of assembled code is given using its hexadecimal representation in character form. Easy to read by human beings. Each byte of object code is stored as a single byte.

Begin

read Header record

verify program name and length read first Text record

while record type is != 'E' do begin

{if object code is in character form, convert into internal representation}

move object code to specified location in memory read next object program record

end

jump to address specified in End record

end

Figure: Algorithm for an absolute loader

Example:

Program to find SUM=ALPHA + BETA

LOCCTR	SOURCE STATEMENTS			OBJECT CODE
	ARTH	START	1000	
1000		LDA	ALPHA	001009
1003		ADD	BETA	18100C
1006		STA	SUM	0C100F
1009	ALPHA	WORD	4	000004
100C	BETA	WORD	2	000002
100F	SUM	RESW	1	
1012		END	ARTH	

OPTAB		
MNEMONIC	OPCODE	
LDA	00	
ADD	18	
STA	0C	

SYMTAB		
LABEL	ADDRESS	
ALPHA	1009	
BETA	100C	
SUM	100F	

MEMORY ADDRESS	CONTENTS
0000	XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX
1000	001009 18100C 0C100F
	000004 000002
1012	
1015	

Fig: Program loaded in memory at the address 1000H

OBJECT PROGRAM

HARTH 001000000012

T0010000F00100918100C0C100F0000040000

02 E001000

Figure: Absolute Object Program for the above source program.

2. A Simple Bootstrap Loader

10. About Bootstrap Loader

When a computer is first turned on or restarted, a special type of absolute loader, called bootstrap loader is executed. This bootstrap loads the first program to be run by the computer -- usually an operating system. The bootstrap itself begins at address 0. It loads the OS starting address 0x80. No header record or control information, the object code is consecutive bytes of memory.

The algorithm for the bootstrap loader is as follows

Begin

X=0x80 (the address of the next memory location to be loaded

LOOP

```
A-GETC (and convert it from the ASCII character code to the value of the hexadecimal digit) save the value in the high-order 4 bits of S  A\text{-GETC}  combine the value to form one byte A- (A+S) store the value (in A) to the address in register X  X\text{-}X\text{+}1
```

End

It uses a subroutine GETC, which is

```
GETC A-read one character if A=0x04 then jump to 0x80 if A<48 then GETC A \leftarrow A-48 \ (0x30) if A<10 then return A \leftarrow A-7 \ return
```

3. Relocating Loader

The loader that allow program relocation is called relocating loader.

```
BEGIN
```

```
Get PROGADDR from operating system
  while not end of input do
    BEGIN
      read next input record
      while record type != 'E' do
        BEGIN
             read next input record
             while record type = 'T' then
               BEGIN
                    move object code from record to location PROGADDR + specified address.
               End
             While record type = 'M'
                    Add PROGADDR at the location PROGADDR + SPECIFIED ADDRESS.
        END
     END
END
```

Figure: SIC/XE relocation loader algorithm

LOCCTR	SOURCE STATEMENTS		OBJECT CODE	
	READ	START	0	
0000		+JSUB	TEST	4B10000C
0004		RD	INPUT	DB2003
0007		STCH	DATA	572001
000A	INPUT	BYTE	X'F1'	F1
000B	DATA	RESB	1	
000C	TEST	TD	INPUT	E32FFB
000F		JEQ	*-3	332FFA
0012		RSUB		4C0000
0015		END	READ	

SYMTAB		
LABEL	ADDRESS	
INPUT	000A	
DATA	000B	
TEST	000C	

OPTAB		
MNEMONIC	OPCODE	
JSUB	48	
RD	D8	
STCH	54	
TD	E0	
JEQ	30	
RSUB	4C	

OBJECT PROGRAM

HREAD 000000000015

T0000000B4B10100CDB2003572001F1

T00000C09E32FFB332FFA4C0000 M00000105

E000000

MEMORY ADDRESS	CONTENTS
0000	XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX
1000	4B10100C DB2003 572001 F1
100C	E32FFB 332FFA 4C0000
1015	

Fig: Program loaded in memory at the address 1000H because there is no space at address 0000H.

Relocating loader add 1000H at the location 1000H + 000001.