GROMACS Tutorial 4 - Methane free energy of solvation

In this tutorial I'll show you how to perform a free energy of solvation simulation using GROMACS, as well as how to calculate the free energy change using MBAR (http://dx.doi.org/10.1063/1.2978177). As always, this tutorial builds off of the previous ones, especially tutorials 1 and 2.

I recommend visiting the Alchemistry (http://alchemistry.org) website if you are unfamiliar with free energy calculations. This page (http://www.alchemistry.org/wiki/Example:_Solvation_of_OPLS-AA_Ethanol_in_TIP3P_Water) in particular is relevant. This tutorial follows the direct calculation. State A for us is a methane fully interacting in water. State B will be a methane with all van der Waals and Coulomb interactions with the water turned off; the methane can interact with itself and the water can interact with itself but not with each other. It's as if we have taken the methane out of the water and put it into a vacuum, while somewhere else we still have the water the methane was in. We have 15 total states where we will be linearly turning off the electrostatic interactions and then using a soft-core potential to turn off the van der Waals interactions.

Setup

Box creation

Reuse the methane.pdb and topol.top files that we've been using so far for the OPLS methane and TIP4PEW water. Remove any solvent from the topol.top file (delete the last line which starts with SOL). Make sure that the name for the methane under [moleculetype] is 'Methane' (no quotes), as well as under [molecules]. We'll be using one methane, so if you have more listed, change it to 1 now.

This time we're using a different box type so that we won't have to use as much water. We'll use a dodecahedron box at 1.2 nm out in each direction from the methane. First create the box:

```
$ gmx editconf -f methane.pdb -bt dodec -d 1.2 -o box.gro
```

Now fill with solvent:

```
$ gmx solvate -cs tip4p -cp box.gro -o conf.gro -p topol.top
```

Parameter files

The parameter files we'll be using are almost exactly the same as previous tutorials, except we're adding a free energy section in order to slowly turn off our methane. Additionally we need a parameter file for each state. We have 15 minimizations, 15 equilibrations, etc. But we'll use a script to simply update the appropriate values in a template, so we actually only will have to have one for each part of the simulation. At each state we'll do our two minimizations, equilibrate at NVT for 100 ps, equilibrate at NPT for 1 ns, and then do a production run for 5 ns.

The files can be downloaded here (../../_downloads/39f3d0636f60d677880dfd7e058449ed/mdp.tar.gz).

Here's an explanation of some of these new values:

parameter	value	explanation			
free-energy	yes	Do a free energy simulation.			

parameter	value	explanation
init-la mbda-sta te	MYLAMBDA	The value I have in the files is not actually what will be present when we run the simulation. This is a placeholder for an integer number. We are simulating 15 different states, so this number will range from 0 through 14. Our script will replace it for each state.
calc-lambda-neighbors	-1	The delta H values will be written for each state. Necessary for MBAR.
vdw-la mb da s	see file	We're turning off VDW at 0.1- lambda increments after electrostatics are off. init-lambda- state=0 corresponds to the first value in this array, init-lambda- state=1 the second, and so on.
coul-la mbdas	see file	We're turning off electrostatics at 0.25-lambda increments first. Just like vdw-lambdas, the initlambda-state indicates which column is being used.
couple-moltype	Methane	Matches the name of the [moleculetype] in the topology file that we are coupling/decoupling
couple-la mbda 0	vdw-q	When lambda is 0 (state A) both VDW and electrostatics are completely on.
couple-la mbda 1	none	When lambda is 1 (state B) no nonbonded interations are on.
couple-intra mol	no	Intramolecular terms are not turned off. Usually what you want so you don't have to run it again in vacuum.
nstdhdl	100	How often in steps we're outputting dHdlambda
sc-alpha	0.5	We're using a soft-core potential for VDW. This parameter is a term in the soft-core function. See the manual.
sc-power	1	See above.
sc-sigma	0.3	See above.

parameter	value	explanation
sc-coul	no	Don't use soft core for
		electrostatics

One last note on the parameter files: we're using the sd integrator, which stands for stochastic dynamics. sd itself controls the temperature, so we're no longer using Nose-Hoover. If you were to use md you would get a warning that you may not be properly sampling the decoupled state.

Simulation

As stated earlier we're actually running 15 simulations. To make this easier and in order to avoid having 15 different mdp files as inputs, use the following bash script to loop through and run each state:

```
#!/bin/bash
set -e
for ((i=0;i<15;i++)); do
   sed 's/MYLAMBDA/'$i'/g' mdp/min.mdp > grompp.mdp
   if [[ $i -eq 0 ]]; then
       gmx grompp -o min.$i -pp min.$i -po min.$i
    else
       gmx grompp -c prd.$(($i-1)).gro -o min.$i -pp min.$i -po min.$i
   fi
   gmx mdrun -deffnm min.$i
    sed 's/MYLAMBDA/'$i'/g' mdp/min2.mdp > grompp.mdp
   gmx grompp -o min2.$i -c min.$i -t min.$i -pp min2.$i -po min2.$i -maxwarn 1
   gmx mdrun -deffnm min2.$i
    sed 's/MYLAMBDA/'$i'/g' mdp/eql.mdp > grompp.mdp
   gmx grompp -o eql.$i -c min2.$i -t min2.$i -pp eql.$i -po eql.$i
   gmx mdrun -deffnm eql.$i
    sed 's/MYLAMBDA/'i'/g' mdp/eq12.mdp > grompp.mdp
   gmx grompp -o eql2.$i -c eql.$i -t eql.$i -pp eql2.$i -po eql2.$i
   gmx mdrun -deffnm eql2.$i
   sed 's/MYLAMBDA/'$i'/g' mdp/prd.mdp > grompp.mdp
   gmx grompp -o prd.$i -c eql2.$i -t eql2.$i -pp prd.$i -po prd.$i
   gmx mdrun -deffnm prd.$i
done
```

The script uses a for loop going from i=0 through i=14. In each iteration it uses sed to find and replace the keyword MYLAMBDA I placed in our mdp file template with the correct lambda state. It saves this file as grompp.mdp which is the default file name that *gmx grompp* looks for. All of our output is suffixed with the lambda state. Additionally all lambda states greater than 0 use the previous state's final structure file. This isn't entirely necessary for methane decoupling, but it could possibly be beneficial in other systems.

Put the above in a script named $\, run$. The script assumes you have downloaded and placed the mdp files in a subdirectory named $\, mdp$. Then do:

```
$ chmod +x run
$ ./run
```

Analysis

We'll be using MBAR, specifically the python implementation known as pymbar. The alchemical analysis (https://github.com/MobleyLab/alchemical-analysis) script provides an easy way to perform the calculation and actually provides several different methods with error analysis.

After downloading and installing the script, run it in the directory with the results:

```
$ alchemical_analysis -p prd. -u kcal
```

Your output should look something like this:


States	TI (kcal	/mol)	TI-CUBIC (kcal	/mol)	DEXP (kcal	./mol)	IEXP (
0 1	0.002	+-	0.000	0.002	+-	0.000	0.002	+-	0.000	0.001
1 2	-0.000	+-	0.000	-0.000	+ -	0.000	-0.001	+-	0.000	-0.000
2 3	-0.003	+-	0.000	-0.003	+ -	0.000	-0.002	+-	0.000	-0.003
3 4	-0.005	+-	0.000	-0.005	+-	0.000	-0.005	+-	0.000	-0.006
4 5	0.093	+-	0.002	0.094	+ -	0.002	0.090	+-	0.005	0.096
5 6	0.063	+-	0.002	0.065	+-	0.003	0.055	+-	0.010	0.063
6 7	0.013	+-	0.003	0.014	+-	0.003	0.025	+-	0.006	0.009
7 8	-0.055	+-	0.003	-0.052	+-	0.004	-0.051	+-	0.008	-0.050
8 9	-0.157	+-	0.004	-0.151	+ -	0.005	-0.149	+-	0.014	-0.155
9 10	-0.338	+-	0.006	-0.324	+ -	0.006	-0.306	+-	0.020	-0.332
10 11	-0.602	+-	0.005	-0.621	+-	0.006	-0.595	+-	0.016	-0.631
11 12	-0.674	+-	0.003	-0.708	+-	0.003	-0.708	+-	0.005	-0.709
12 13	-0.437	+-	0.001	-0.437	+-	0.002	-0.435	+-	0.002	-0.441
13 14	-0.138	+-	0.001	-0.134	+ -	0.001	-0.131	+-	0.001	-0.132
coulomb:	-0.007	+-	0.001	-0.007	+-	0.001	-0.006	+-	0.001	-0.007
vdWaals:	-2.232	+-	0.015	-2.255	+ -	0.015	-2.205	+-	0.033	-2.281
TOTAL:	-2.238	+-	0.015	-2.262	+-	0.015	-2.211	+-	0.033	-2.288

This is the free energy of removing a methane, so the free energy of solvation is actually negative one times this, since it is the reverse process. Our result of 2.289 kcal / mol is comparable to published figures. In a paper that simulated OPLS methane with TIP3P (http://dx.doi.org/10.1063/1.1587119), they achieved a result of 2.44 kcal/mol. The difference can probably be attributed to using a different water model.

Note that the script provides six different results from six different methods. Some of these methods are better than others, but the fact that all six are close to each other tells us we probably sampled enough states to get an accurate number. MBAR is one of the better methods, although BAR and TI are good as well. I reran the script to gather some more analysis:


```
$ alchemical_analysis -p prd. -u kcal -g -f 20
```

Here is a visual comparison of the calculated value for each segment:




I can see that one of the methods (DEXP) gets a different results for calculations between states 5 and 6 as well as between 6 and 7. I'm not too concerned about this, since the other methods line up well and DEXP is not one of the "better" methods.

And here is the curve:



Here we are looking for places where the curvature is high. The curvature is higher around states 10, 11, and 12. Depending on our application, we might want to possibly sample more states in that area.

Lastly, here is a plot of the result calculated as a function of time, both running the simulation forward and running it in reverse:



The point here is that we're looking to make sure that the simulation is well-equilibrated; otherwise, the result will not be correct. If the curves were flat for any significant portion of the first part of the plot, this would indicate our system may not be well equilibrated before we started the simulation. We could discard that non-equilibrated data and redo the calculation.

There are a couple of other command line flags you can use with the alchemical_analysis script. Be sure to checkout the homepage of the script and the paper on best practices in free energy analysis (https://dx.doi.org/10.1007/s10822-015-9840-9) which goes much more into detail on these and other plots. I won't go into detail of all the options here.

Summary

In this tutorial we performed a free energy simulation on methane in water. We turned off electrostatics linearly first, and then we used a soft-core potential to turn off the van der Waals interactions. The intramolecular interactions for methane remained on, so its as if we were removing the methane from the water and placing it in a vacuum. Our result of 2.289 kcal /mol is comparable to published results.

barnett.science GROMACS Tutorials by Wes Barnett (https://barnett.science/tutorials) is licensed under a Creative Commons Attribution-ShareAlike 4.0 International License (https://creativecommons.org/licenses/by-sa/4.0/).

© Copyright 2015 – 2020, Željko Svedružić | Zeljko M. Svedruzic. Created using Sphinx (http://sphinx-doc.org/) 3.2.1. Back to top