Sequencer64 Developer Reference Manual 0.9.17

Generated by Doxygen 1.8.11

Contents

1	Seq	uencer6	64		1
	1.1	Introdu	uction		1
2	MID	l File Pa	ırsing in S	Sequencer64	3
	2.1	Introdu	uction		3
	2.2	SMF 1	Parsing .		3
		2.2.1	MIDI File	Header, MThd	3
		2.2.2	MIDI Tra	ck, MTrk	4
			2.2.2.1	Channel Events	4
			2.2.2.2	Meta Events	5
		2.2.3	Meta Eve	ents Summary	6
			2.2.3.1	Sequence Number (0x00)	6
			2.2.3.2	Track/Sequence Name (0x03)	7
			2.2.3.3	End of Track (0x2F)	7
			2.2.3.4	Set Tempo Event (0x51)	7
			2.2.3.5	Time Signature Event (0x58)	8
			2.2.3.6	SysEx Event (0xF0)	9
			2.2.3.7	Sequencer Specific (0x7F)	10
			2.2.3.8	Non-Specific End of Sequence	10
	2.3	SMF 0	Parsing .		10
	24	Runnir	na Status		11

iv CONTENTS

3	JAC	CK, Live, and Song Modes in Sequencer64	13
	3.1	Introduction	13
	3.2	JACK Functions	13
		3.2.1 jack_client_open()	14
		3.2.2 jack_on_shutdown()	14
		3.2.3 jack_set_sync_callback()	14
		3.2.4 jack_set_process_callback()	15
		3.2.5 jack_set_session_callback()	15
		3.2.6 jack_activate()	15
		3.2.7 jack_release_timebase()	15
		3.2.8 jack_client_close()	15
		3.2.9 jack_transport_start()	15
		3.2.10 jack_transport_stop()	15
		3.2.11 jack_transport_locate()	15
		3.2.12 jack_transport_reposition()	16
		3.2.13 jack_transport_query()	16
	3.3	Modes Operation	16
		3.3.1 No JACK, Live Mode	16
		3.3.2 No JACK, Song Mode	16
		3.3.3 JACK Transport	17
	3.4	Breakage	17
	3.5	JACK References	18
4	Heer	r Testing of Sequencer64 with Yoshimi	19
•	4.1	Introduction	19
	4.1	Smoke Test	19
	4.3	Tests in the Patterns Window	20
		4.3.1 Button Clicks on a Pattern	21
		· · · · · · · · · · · · · · · · · · ·	
	4.4	4.3.3 The Sequencer64 User File	21
	4.4	Tests Using Valgrind	21
		4.4.1 Valgrind Suppressions	22
		4.4.2 Full Valgrind Leak-Checking	22
		4.4.2.1 Leak-Checking Basic Operation	23
	4.5	Specific Fault Debugging	23
	4.6	Snipping of a MIDI file.	23

CONTENTS

5	Lice	Licenses				
	5.1	License Terms for the This Project	25			
	5.2	XPC Application License	25			
	5.3	XPC Library License	26			
	5.4	XPC Documentation License	26			
	5.5	XPC Affero License	27			
	5.6	XPC License Summary	27			
6	Todo	o List	29			
7	Depi	recated List	31			
8	Nam	nespace Index	33			
	8.1	Namespace List	33			
9	Hiera	archical Index	35			
	9.1	Class Hierarchy	35			
10	Data	Structure Index	37			
	10.1	Data Structures	37			
11		nespace Documentation	41			
		Gtk Namespace Reference	41			
	11.2	seq64 Namespace Reference	41			
		11.2.1 Detailed Description	51			
		11.2.2 Typedef Documentation	51			
		11.2.2.1 midibyte	51			
		11.2.2.2 bussbyte	51			
		11.2.2.3 midishort	51			
		11.2.2.4 midilong	51			
		11.2.2.5 midipulse	51			
		11.2.3 Enumeration Type Documentation	51			
		11.2.3.1 wave_type_t	51			
		11.2.3.2 seq_modifier_t	52			

vi

	11.2.3.3	seq_event_type_t	52
	11.2.3.4	seq_scroll_direction_t	53
	11.2.3.5	clock_e	53
	11.2.3.6	interaction_method_t	53
	11.2.3.7	c_music_scales	54
	11.2.3.8	draw_type_t	54
	11.2.3.9	mouse_action_e	54
	11.2.3.10	edit_action_t	55
11.2.4	Function	Documentation	55
	11.2.4.1	extract_timing_numbers(const_std::string &s, std::string ∂_1, std::string ∂_2, std::string ∂_3, std::string &fraction)	55
	11.2.4.2	pulses_to_string(midipulse p)	56
	11.2.4.3	pulses_to_measurestring(midipulse p, const midi_timing &seqparms)	56
	11.2.4.4	pulses_to_midi_measures(midipulse p, const midi_timing &seqparms, midi_← measures &measures)	56
	11.2.4.5	pulses_to_timestring(midipulse p, int bpm, int ppqn)	57
	11.2.4.6	pulses_to_timestring(midipulse p, const midi_timing &timinginfo)	57
	11.2.4.7	measurestring_to_pulses(const std::string &measures, const midi_timing &seq-parms)	57
	11.2.4.8	midi_measures_to_pulses(const midi_measures &measures, const midi_timing &seqparms)	58
	11.2.4.9	timestring_to_pulses(const std::string ×tring, int bpm, int ppqn)	58
	11.2.4.10	string_to_pulses(const std::string &s, const midi_timing &mt)	58
	11.2.4.11	string_to_midibyte(const std::string &s)	59
	11.2.4.12	shorten_file_spec(const std::string &fpath, int leng)	59
	11.2.4.13	string_not_void(const std::string &s)	59
	11.2.4.14	string_is_void(const std::string &s)	60
	11.2.4.15	strings_match(const std::string ⌖, const std::string &x)	60
	11.2.4.16	log2_time_sig_value(int tsd)	60
	11.2.4.17	tempo_us_to_bytes(midibyte t[3], int tempo_us)	61
	11.2.4.18	zoom_power_of_2(int ppqn)	61
	11.2.4.19	beats_per_minute_from_tempo_us(double tempous)	61

CONTENTS vii

11.2.4.20 tempo_us_from_beats_per_minute(double bpm)	62
11.2.4.21 tempo_to_us(int bpm)	62
11.2.4.22 pulse_length_us(int bpm, int ppqn)	62
11.2.4.23 delta_time_us_to_ticks(unsigned long us, int bpm, int ppqn)	62
11.2.4.24 ticks_to_delta_time_us(midipulse delta_ticks, int bpm, int ppqn)	63
11.2.4.25 clock_tick_duration_bogus(int bpm, int ppqn)	63
11.2.4.26 clock_ticks_from_ppqn(int ppqn)	64
11.2.4.27 double_ticks_from_ppqn(int ppqn)	64
11.2.4.28 pulses_per_measure(int ppqn=SEQ64_DEFAULT_PPQN)	64
11.2.4.29 measures_to_ticks(int bpm, int ppqn, int bw, int measures=1)	64
11.2.4.30 wave_func(double angle, wave_type_t wavetype)	65
11.2.4.31 help_check(int argc, char *argv[])	65
11.2.4.32 parse_options_files(perform &p, int argc, char *argv[])	66
11.2.4.33 parse_command_line_options(int argc, char *argv[])	66
11.2.4.34 write_options_files(const perform &p)	67
11.2.4.35 build_details()	67
11.2.4.36 to_string(const event &ev)	67
11.2.4.37 file_access(const std::string &targetfile, int mode)	67
11.2.4.38 file_exists(const std::string &filename)	67
11.2.4.39 file_readable(const std::string &filename)	67
11.2.4.40 file_writable(const std::string &filename)	68
11.2.4.41 file_accessible(const std::string &filename)	68
11.2.4.42 file_executable(const std::string &filename)	68
11.2.4.43 file_is_directory(const std::string &filename)	68
11.2.4.44 make_directory(const std::string &pathname)	69
11.2.4.45 ppqn_is_valid(int ppqn)	69
11.2.4.46 jack_sync_callback(jack_transport_state_t state, jack_position_t *pos, void *arg)	69
11.2.4.47 jack_shutdown_callback(void *arg)	70
11.2.4.48 jack_timebase_callback(jack_transport_state_t state, jack_nframes_t nframes, jack_position_t *pos, int new_pos, void *arg)	70
11.2.4.49 jack_process_callback(jack_nframes_t nframes, void *arg)	71

viii CONTENTS

	11.2.4.50 jack_session_callback(jack_session_event_t *ev, void *arg)	71
	11.2.4.51 keyval_name(unsigned int key)	71
	11.2.4.52 keyval_normalize(keys_perform_transfer &k)	72
	11.2.4.53 create_lash_driver(perform &p, int argc, char **argv)	72
	11.2.4.54 lash_driver()	72
	11.2.4.55 delete_lash_driver()	73
	11.2.4.56 output_thread_func(void *p)	73
	11.2.4.57 input_thread_func(void *myperf)	73
	11.2.4.58 rc()	73
	11.2.4.59 usr()	73
	11.2.4.60 choose_ppqn(int ppqn)	73
	11.2.4.61 min(long a, long b)	74
	11.2.4.62 make_section_name(const std::string &label, int value)	74
	11.2.4.63 font_render()	74
	11.2.4.64 adjustment_dummy()	75
	11.2.4.65 update_mainwid_sequences()	75
	11.2.4.66 update_perfedit_sequences()	75
	11.2.4.67 FF_RW_timeout(void *)	75
	11.2.4.68 clamp(long val, long low, long hi)	75
	11.2.4.69 clamp(long val, long low, long hi)	75
11.2.5	Variable Documentation	75
	11.2.5.1 c_controller_names	75
	11.2.5.2 EVENT_STATUS_BIT	75
	11.2.5.3 EVENT_ANY	75
	11.2.5.4 EVENT_NOTE_OFF	76
	11.2.5.5 EVENT_NOTE_ON	76
	11.2.5.6 EVENT_AFTERTOUCH	76
	11.2.5.7 EVENT_CONTROL_CHANGE	76
	11.2.5.8 EVENT_PROGRAM_CHANGE	76
	11.2.5.9 EVENT_CHANNEL_PRESSURE	76

CONTENTS

11.2.5.10 EVENT_PITCH_WHEEL	76
11.2.5.11 EVENT_MIDI_SYSEX	76
11.2.5.12 EVENT_MIDI_QUARTER_FRAME	76
11.2.5.13 EVENT_MIDI_SONG_POS	76
11.2.5.14 EVENT_MIDI_SONG_SELECT	76
11.2.5.15 EVENT_MIDI_SONG_F4	76
11.2.5.16 EVENT_MIDI_SONG_F5	76
11.2.5.17 EVENT_MIDI_TUNE_SELECT	76
11.2.5.18 EVENT_MIDI_SYSEX_END	76
11.2.5.19 EVENT_MIDI_SYSEX_CONTINUE	76
11.2.5.20 EVENT_MIDI_CLOCK	76
11.2.5.21 EVENT_MIDI_SONG_F9	77
11.2.5.22 EVENT_MIDI_START	77
11.2.5.23 EVENT_MIDI_CONTINUE	77
11.2.5.24 EVENT_MIDI_STOP	77
11.2.5.25 EVENT_MIDI_SONG_FD	77
11.2.5.26 EVENT_MIDI_ACTIVE_SENS	77
11.2.5.27 EVENT_MIDI_RESET	77
11.2.5.28 EVENT_MIDI_META	77
11.2.5.29 EVENT_NULL_CHANNEL	77
11.2.5.30 EVENT_GET_CHAN_MASK	77
11.2.5.31 EVENT_CLEAR_CHAN_MASK	77
11.2.5.32 EVENTS_ALL	77
11.2.5.33 EVENTS_UNSELECTED	77
11.2.5.34 c_midibus_output_size	77
11.2.5.35 c_midibus_input_size	77
11.2.5.36 c_midibus_sysex_chunk	78
11.2.5.37 c_midibus	78
11.2.5.38 c_midich	79
11.2.5.39 c_midiclocks	79

CONTENTS

11.2.5.40 c_triggers
11.2.5.41 c_notes
11.2.5.42 c_timesig
11.2.5.43 c_bpmtag
11.2.5.44 c_triggers_new
11.2.5.45 c_mutegroups
11.2.5.46 c_midictrl
11.2.5.47 c_musickey
11.2.5.48 c_musicscale
11.2.5.49 c_backsequence
11.2.5.50 c_transpose
11.2.5.51 c_perf_bp_mes
11.2.5.52 c_perf_bw
11.2.5.53 c_midi_track_ctrl
11.2.5.54 c_midi_control_bpm_up
11.2.5.55 c_midi_control_bpm_dn
11.2.5.56 c_midi_control_ss_up
11.2.5.57 c_midi_control_ss_dn
11.2.5.58 c_midi_control_mod_replace
11.2.5.59 c_midi_control_mod_snapshot
11.2.5.60 c_midi_control_mod_queue
11.2.5.61 c_midi_control_mod_gmute
11.2.5.62 c_midi_control_mod_glearn
11.2.5.63 c_midi_control_play_ss
11.2.5.64 c_midi_controls
11.2.5.65 c_scales_policy
11.2.5.66 c_scales_transpose_up
11.2.5.67 c_scales_transpose_dn
11.2.5.68 c_scales_text
11.2.5.69 c_key_text

CONTENTS xi

11.2.5.70 c_interval_text
11.2.5.71 c_chord_text
11.2.5.72 c_max_instruments
11.2.5.73 c_max_busses
11.2.5.74 versiontext
11.2.5.75 long_options
11.2.5.76 s_arg_list
11.2.5.77 s_help_1a
11.2.5.78 s_help_1b
11.2.5.79 s_help_2
11.2.5.80 s_help_3
11.2.5.81 s_help_4
11.2.5.82 s_build_highlight_empty
11.2.5.83 s_build_lash_support
11.2.5.84 s_build_jack_support
11.2.5.85 s_build_jack_session
11.2.5.86 s_build_pause_support
11.2.5.87 s_build_use_event_map
11.2.5.88 s_build_chord_generator
11.2.5.89 s_build_edit_highlight
11.2.5.90 s_build_timesig_tempo
11.2.5.91 s_build_midi_vector
11.2.5.92 s_build_solid_grid
11.2.5.93 s_build_follow_progress
11.2.5.94 s_statistics_support
11.2.5.95 s_character_mapping
11.2.5.96 s_global_lash_driver
11.2.5.97 c_status_replace
11.2.5.98 c_status_snapshot
11.2.5.99 c_status_queue
11.2.5.100g_rc_settings
11.2.5.101g_user_settings
11.2.5.102s_handlesize
11.2.5.103s_jitter_amount
11.2.5.104gs_mainwid_pointer
11.2.5.105c_mainwid_x
11.2.5.106c_mainwid_y
11.2.5.107gs_perfedit_pointer_0
11.2.5.108gs_perfedit_pointer_1
11.2.5.109s_handlesize

xii CONTENTS

12	Data	Structu	ire Docun	nentation	85
	12.1	seq64:	:AbstractP	erfInput Class Reference	85
		12.1.1	Construc	tor & Destructor Documentation	86
			12.1.1.1	AbstractPerfInput()	86
			12.1.1.2	~AbstractPerfInput()	86
		12.1.2	Member	Function Documentation	86
			12.1.2.1	on_button_press_event(GdkEventButton *a_ev, perfroll &roll)=0	86
			12.1.2.2	on_button_release_event(GdkEventButton *a_ev, perfroll &roll)=0	86
			12.1.2.3	on_motion_notify_event(GdkEventMotion *a_ev, perfroll &roll)=0	86
		12.1.3	Field Doo	sumentation	86
			12.1.3.1	m_adding_pressed	86
	12.2	seq64:	:automute	Class Reference	86
		12.2.1	Detailed	Description	87
		12.2.2	Construc	tor & Destructor Documentation	87
			12.2.2.1	automutex()	87
			12.2.2.2	automutex(const automutex &)	87
			12.2.2.3	automutex(mutex &my_mutex)	87
			12.2.2.4	~automutex()	87
		12.2.3	Member	Function Documentation	87
			12.2.3.1	operator=(const automutex &)	87
		12.2.4	Field Doo	umentation	87
			12.2.4.1	m_safety_mutex	87
	12.3	seq64:	click Class	s Reference	88
		12.3.1	Detailed	Description	89
		12.3.2	Construc	tor & Destructor Documentation	89
			12.3.2.1	click()	89
			12.3.2.2	click(int x, int y, int button=SEQ64_CLICK_BUTTON_LEFT, bool press=true, seq_modifier_t modkey=SEQ64_NO_MASK)	89
			12.3.2.3	click(const click &rhs)	89
		12.3.3	Member	Function Documentation	89
			12.3.3.1	operator=(const click &rhs)	89

CONTENTS xiii

	12.3.3.2 is_press() const	90
	12.3.3.3 is_left() const	90
	12.3.3.4 is_middle() const	90
	12.3.3.5 is_right() const	90
	12.3.3.6 x() const	90
	12.3.3.7 y() const	90
	12.3.3.8 button() const	90
	12.3.3.9 modifier() const	90
	12.3.3.10 mod_control() const	90
	12.3.3.11 mod_control_shift() const	90
	12.3.3.12 mod_super() const	90
12.3	.4 Field Documentation	90
	12.3.4.1 m_is_press	90
	12.3.4.2 m_x	90
	12.3.4.3 m_y	90
	12.3.4.4 m_button	90
	12.3.4.5 m_modifier	91
12.4 seq6	4::condition_var Class Reference	91
12.4	.1 Detailed Description	92
12.4	.2 Constructor & Destructor Documentation	92
	12.4.2.1 condition_var()	92
12.4	.3 Member Function Documentation	92
	12.4.3.1 wait()	92
	12.4.3.2 signal()	92
12.4	.4 Field Documentation	92
	12.4.4.1 sm_cond	92
	12.4.4.2 m_cond	92
12.5 seq6	4::configfile Class Reference	92
12.5	.1 Constructor & Destructor Documentation	94
	12.5.1.1 configfile(const std::string &name)	94

xiv CONTENTS

		12.5.1.2	~configfile()	94
	12.5.2	Member	Function Documentation	94
		12.5.2.1	next_data_line(std::ifstream &file)	94
		12.5.2.2	line_after(std::ifstream &file, const std::string &tag)	94
		12.5.2.3	parse(perform &perf)=0	95
		12.5.2.4	write(const perform &perf)=0	95
	12.5.3	Field Doo	cumentation	95
		12.5.3.1	m_name	95
		12.5.3.2	m_d	95
		12.5.3.3	m_line	95
12.6	seq64:	:editable_e	event Class Reference	95
	12.6.1	Detailed	Description	99
	12.6.2	Member	Enumeration Documentation	99
		12.6.2.1	category_t	99
		12.6.2.2	timestamp_format_t	100
	12.6.3	Construc	tor & Destructor Documentation	100
		12.6.3.1	editable_event()	100
		12.6.3.2	editable_event(const editable_events &parent)	100
		12.6.3.3	editable_event(const editable_events &parent, const event &ev)	100
		12.6.3.4	editable_event(const editable_event &rhs)	100
		12.6.3.5	~editable_event()	101
	12.6.4	Member	Function Documentation	101
		12.6.4.1	value_to_name(midibyte value, category_t cat)	101
		12.6.4.2	name_to_value(const std::string &name, category_t cat)	101
		12.6.4.3	operator=(const editable_event &rhs)	101
		12.6.4.4	parent() const	101
		12.6.4.5	category() const	101
		12.6.4.6	category(category_t c)	101
		12.6.4.7	category_string() const	102
		12.6.4.8	category(const std::string &cs)	102

CONTENTS xv

	12.6.4.9	timestamp_string() const	102
	12.6.4.10	timestamp() const	102
	12.6.4.11	timestamp(midipulse ts)	102
	12.6.4.12	timestamp(const std::string &ts_string)	102
	12.6.4.13	time_as_pulses()	102
	12.6.4.14	time_as_measures()	102
	12.6.4.15	time_as_minutes()	102
	12.6.4.16	set_status_from_string(const std::string &ts, const std::string &s, const std::string &sd0, const std::string &sd1)	103
	12.6.4.17	format_timestamp()	103
	12.6.4.18	stock_event_string()	103
	12.6.4.19	status_string() const	103
	12.6.4.20	meta_string() const	103
	12.6.4.21	seqspec_string() const	103
	12.6.4.22	channel_string() const	103
	12.6.4.23	data_string() const	103
	12.6.4.24	analyze()	103
12.6.5	Field Doc	umentation	104
	12.6.5.1	sm_category_names	104
	12.6.5.2	sm_channel_event_names	104
	12.6.5.3	sm_system_event_names	104
	12.6.5.4	sm_meta_event_names	104
	12.6.5.5	sm_prop_event_names	104
	12.6.5.6	sm_category_arrays	105
	12.6.5.7	m_parent	105
	12.6.5.8	m_category	105
	12.6.5.9	m_name_category	105
	12.6.5.10	m_format_timestamp	105
	12.6.5.11	m_name_timestamp	105
	12.6.5.12	m_name_status	105
	12.6.5.13	m_name_meta	105

xvi CONTENTS

12.6.5.14 m_name_seqspec	. 105
12.6.5.15 m_name_channel	. 105
12.6.5.16 m_name_data	. 105
12.7 seq64::editable_events Class Reference	. 105
12.7.1 Member Typedef Documentation	. 107
12.7.1.1 Key	. 107
12.7.1.2 EventsPair	. 107
12.7.1.3 Events	. 107
12.7.1.4 iterator	. 107
12.7.1.5 const_iterator	. 107
12.7.2 Constructor & Destructor Documentation	. 107
12.7.2.1 editable_events()	. 107
12.7.2.2 editable_events(sequence &seq, int bpm)	. 107
12.7.2.3 editable_events(const editable_events &rhs)	. 108
12.7.2.4 ~editable_events()	. 108
12.7.3 Member Function Documentation	. 108
12.7.3.1 operator=(const editable_events &rhs)	. 108
12.7.3.2 timing() const	. 108
12.7.3.3 string_to_pulses(const std::string &ts_string) const	. 108
12.7.3.4 load_events()	. 108
12.7.3.5 save_events()	. 109
12.7.3.6 events()	. 109
12.7.3.7 begin()	. 109
12.7.3.8 begin() const	. 109
12.7.3.9 end()	. 109
12.7.3.10 end() const	. 109
12.7.3.11 dref(iterator ie)	. 109
12.7.3.12 dref(const_iterator ie)	. 109
12.7.3.13 count() const	. 109
12.7.3.14 add(const event &e)	. 109

CONTENTS xvii

		12.7.3.15 add(const editable_event &e)
		12.7.3.16 replace(iterator ie, const editable_event &e)
		12.7.3.17 remove(iterator ie)
		12.7.3.18 clear()
		12.7.3.19 current_event() const
		12.7.3.20 current_event(iterator cei)
	12.7.4	Friends And Related Function Documentation
		12.7.4.1 eventslots
	12.7.5	Field Documentation
		12.7.5.1 m_events
		12.7.5.2 m_current_event
		12.7.5.3 m_sequence
		12.7.5.4 m_midi_parameters
12.8	seq64::	event Class Reference
	12.8.1	Detailed Description
-	12.8.2	Member Typedef Documentation
		12.8.2.1 SysexContainer
-	12.8.3	Constructor & Destructor Documentation
		12.8.3.1 event()
		12.8.3.2 event(const event &rhs)
		12.8.3.3 ~event()
	12.8.4	Member Function Documentation
		12.8.4.1 operator=(const event &rhs)
		12.8.4.2 operator<(const event &rhsevent) const
		12.8.4.3 set_timestamp(midipulse time)
		12.8.4.4 get_timestamp() const
		12.8.4.5 get_channel() const
		12.8.4.6 check_channel(int channel) const
		12.8.4.7 is_channel_msg(midibyte m)
		12.8.4.8 is_one_byte_msg(midibyte m)

xviii CONTENTS

12.8.4.9 is_two_byte_msg(midibyte m)
12.8.4.10 is_note_msg(midibyte m)
12.8.4.11 is_strict_note_msg(midibyte m)
12.8.4.12 is_desired_cc_or_not_cc(midibyte m, midibyte cc, midibyte datum) 120
12.8.4.13 mod_timestamp(midipulse modtick)
12.8.4.14 set_status(midibyte status)
12.8.4.15 set_status(midibyte eventcode, midibyte channel)
12.8.4.16 set_status_keep_channel(midibyte eventcode)
12.8.4.17 set_channel(midibyte channel)
12.8.4.18 get_status() const
12.8.4.19 set_data(midibyte d1)
12.8.4.20 set_data(midibyte d1, midibyte d2)
12.8.4.21 get_data(midibyte &d0, midibyte &d1) const
12.8.4.22 increment_data1()
12.8.4.23 decrement_data1()
12.8.4.24 increment_data2()
12.8.4.25 decrement_data2()
12.8.4.26 append_sysex(midibyte *data, int len)
12.8.4.27 append_sysex(midibyte data)
12.8.4.28 restart_sysex()
12.8.4.29 get_sysex()
12.8.4.30 get_sysex() const
12.8.4.31 set_sysex_size(int len)
12.8.4.32 get_sysex_size() const
12.8.4.33 link(event *ev)
12.8.4.34 get_linked() const
12.8.4.35 is_linked() const
12.8.4.36 clear_link()
12.8.4.37 paint()
12.8.4.38 unpaint()

CONTENTS xix

	12.8.4.39	is_	_pain	ited()) cor	nst					 		 		 		 	123
	12.8.4.40	ma	ark()								 		 		 		 	123
	12.8.4.41	uni	marl	k() .							 		 		 		 	124
	12.8.4.42	is_	_mar	ked() cor	nst					 		 		 		 	124
	12.8.4.43	sel	lect()							 		 		 		 	124
	12.8.4.44	un	sele	ct()							 		 		 		 	124
	12.8.4.45	is_	sele	cted	() cc	nst					 		 		 		 	124
	12.8.4.46	ma	ake_	clock	<() .						 		 		 		 	124
	12.8.4.47	da	ta(in	t ind	ex) (cons	st .				 		 		 	 	 	124
	12.8.4.48	ge	t_no	te() d	cons	st .					 		 		 		 	124
	12.8.4.49	set	t_no	te(m	idiby	/te r	note)) .			 		 		 	 	 	124
	12.8.4.50	ge	t_no	te_v	eloc	ity()	con	st			 		 		 	 	 	124
	12.8.4.51	set	t_no	te_v	eloci	ity(ir	nt ve	el).			 		 		 		 	124
	12.8.4.52	is_	_note	e_on	() co	nst					 		 		 		 	124
	12.8.4.53	is_	note	off	() co	nst					 		 		 		 	124
	12.8.4.54	is_	_note	∌() cc	onst						 		 		 		 	125
	12.8.4.55	is_	_note	off_	_rec	orde	ed()	con	st		 		 		 		 	125
	12.8.4.56	pri	nt()	cons	t .						 		 		 		 	125
	12.8.4.57	ge	t_raı	nk() (cons	it .					 		 		 	 	 	125
12.8.5	Field Docu	ume	enta	tion							 		 		 		 	125
	12.8.5.1	m_	_time	estan	np .						 		 		 	 	 	125
	12.8.5.2	m_	_stat	us .							 		 		 	 	 	125
	12.8.5.3	m_	_cha	nnel							 		 		 	 	 	125
	12.8.5.4	m_	_data	а							 		 		 	 	 	126
	12.8.5.5	m_	_sys	ex .							 		 		 	 	 	126
	12.8.5.6	m_	_sys	ex_s	ize						 		 		 	 	 	126
	12.8.5.7	m_	_linke	ed .							 		 		 	 	 	126
	12.8.5.8	m_	_has	_link	ί						 		 		 	 	 	126
	12.8.5.9	m_	_sele	ected	١						 		 		 	 	 	126
	12.8.5.10	m_	_mar	′ked							 		 		 	 	 	126

CONTENTS

12.8.5.11 m_painted
12.9 seq64::event_list::event_key Class Reference
12.9.1 Detailed Description
12.9.2 Constructor & Destructor Documentation
12.9.2.1 event_key(midipulse tstamp, int rank)
12.9.2.2 event_key(const event &e)
12.9.3 Member Function Documentation
12.9.3.1 operator<(const event_key &rhs) const
12.9.4 Field Documentation
12.9.4.1 m_timestamp
12.9.4.2 m_rank
12.10seq64::event_list Class Reference
12.10.1 Detailed Description
12.10.2 Member Typedef Documentation
12.10.2.1 Events
12.10.2.2 EventsPair
12.10.2.3 iterator
12.10.2.4 const_iterator
12.10.3 Constructor & Destructor Documentation
12.10.3.1 event_list()
12.10.3.2 event_list(const event_list &a_rhs)
12.10.3.3 ~event_list()
12.10.4 Member Function Documentation
12.10.4.1 operator=(const event_list &a_rhs)
12.10.4.2 begin()
12.10.4.3 begin() const
12.10.4.4 end()
12.10.4.5 end() const
12.10.4.6 count() const
12.10.4.7 empty() const

CONTENTS xxi

12.10.4.8 add(const event &e)	131
12.10.4.9 is_modified() const	131
12.10.4.1@nmodify()	131
12.10.4.11remove(iterator ie)	131
12.10.4.12clear()	132
12.10.4.13merge(event_list ⪙, bool presort=true)	132
12.10.4.14dref(iterator ie)	132
12.10.4.15dref(const_iterator ie)	132
12.10.4.1dink_new()	133
12.10.4.17clear_links()	133
12.10.4.18/erify_and_link(midipulse slength)	133
12.10.4.19mark_selected()	133
12.10.4.20mark_out_of_range(midipulse slength)	133
12.10.4.21mark_all()	133
12.10.4.22unmark_all()	133
12.10.4.23remove_marked()	133
12.10.4.24unpaint_all()	134
12.10.4.25count_selected_notes() const	134
12.10.4.26any_selected_notes() const	134
12.10.4.27count_selected_events(midibyte status, midibyte cc) const	134
12.10.4.2&elect_all()	134
12.10.4.29unselect_all()	134
12.10.4.30print() const	134
12.10.4.31events() const	134
12.10.5 Friends And Related Function Documentation	134
12.10.5.1 editable_events	134
12.10.5.2 midi_container	134
12.10.5.3 midi_splitter	135
12.10.5.4 sequence	135
12.10.6 Field Documentation	135

xxii CONTENTS

12.10.6.1 m_events
12.10.6.2 m_is_modified
12.11seq64::eventedit Class Reference
12.11.1 Constructor & Destructor Documentation
12.11.1.1 eventedit(perform &p, sequence &seq)
12.11.1.2 ~eventedit()
12.11.2 Member Function Documentation
12.11.2.1 enqueue_draw()
12.11.2.2 set_seq_title(const std::string &title)
12.11.2.3 set_seq_time_sig(const std::string &sig)
12.11.2.4 set_seq_ppqn(const std::string &p)
12.11.2.5 set_seq_count()
12.11.2.6 set_event_category(const std::string &c)
12.11.2.7 set_event_timestamp(const std::string &ts)
12.11.2.8 set_event_name(const std::string &n)
12.11.2.9 set_event_data_0(const std::string &d)
12.11.2.10set_event_data_1(const std::string &d)
12.11.2.11perf_modify()
12.11.2.12set_dirty(bool flag=true)
12.11.2.13v_adjustment(int value)
12.11.2.14v_adjustment(int value, int lower, int upper)
12.11.2.15change_focus(bool set_it=true)
12.11.2.16close_out()
12.11.2.17handle_close()
12.11.2.18handle_delete()
12.11.2.19handle_insert()
12.11.2.20handle_modify()
12.11.2.21handle_save()
12.11.2.22handle_cancel()
12.11.2.23on_realize()

CONTENTS xxiii

12.11.2.24on_set_focus(Widget *focus)	13
12.11.2.25on_focus_in_event(GdkEventFocus *)	14
12.11.2.26on_focus_out_event(GdkEventFocus *)	14
12.11.2.27on_key_press_event(GdkEventKey *ev)	14
12.11.2.28on_delete_event(GdkEventAny *event)	14
12.11.3 Friends And Related Function Documentation	14
12.11.3.1 eventslots	14
12.11.4 Field Documentation	14
12.11.4.1 m_table	14
12.11.4.2 m_vadjust	1 5
12.11.4.3 m_vscroll	15
12.11.4.4 m_eventslots	15
12.11.4.5 m_htopbox	15
12.11.4.6 m_showbox	15
12.11.4.7 m_editbox	15
12.11.4.8 m_optsbox	15
12.11.4.9 m_bottbox	15
12.11.4.10m_rightbox	15
12.11.4.11m_button_del	15
12.11.4.12m_button_ins	15
12.11.4.13m_button_modify	15
12.11.4.14m_button_save	15
12.11.4.15m_button_cancel	15
12.11.4.16m_label_seq_name	15
12.11.4.17m_label_time_sig	15
12.11.4.18m_label_ppqn	15
12.11.4.19m_label_channel	15
12.11.4.20m_label_ev_count	1 5
12.11.4.21m_label_spacer	1 5
12.11.4.22m_label_modified	1 5

xxiv CONTENTS

12.11.4.23m_label_category	145
12.11.4.24m_entry_ev_timestamp	146
12.11.4.25m_entry_ev_name	146
12.11.4.26m_entry_ev_data_0	146
12.11.4.27m_entry_ev_data_1	146
12.11.4.28m_label_time_fmt	146
12.11.4.29m_label_right	146
12.11.4.30m_seq	146
12.11.4.31m_have_focus	146
12.12seq64::eventslots Class Reference	146
12.12.1 Constructor & Destructor Documentation	151
12.12.1.1 eventslots(perform &p, eventedit &parent, sequence &seq, Gtk::Adjustment &vad-	4-4
just)	
12.12.1.2 ~eventslots()	
12.12.2 Member Function Documentation	
12.12.2.1 event_count() const	151
12.12.2.2 line_count() const	151
12.12.2.3 line_maximum() const	151
12.12.2.4 line_increment() const	151
12.12.2.5 top_index() const	151
12.12.2.6 current_index() const	151
12.12.2.7 pager_index() const	151
12.12.2.8 load_events()	151
12.12.2.9 set_current_event(const_editable_events::iterator_ei, int_index, bool_full_← redraw=true)	151
12.12.2.1@nsert_event(const editable_event &edev)	152
12.12.2.11insert_event(const std::string &evtimestamp, const std::string &evname, const std::string &evdata0, const std::string &evdata1)	152
12.12.2.12delete_current_event()	153
12.12.2.13modify_current_event(const std::string &evtimestamp, const std::string &evname, const std::string &evdata0, const std::string &evdata1)	153
12.12.2.14save_events()	154

CONTENTS xxv

12.12.2.15select_event(int event_index=SEQ64_NULL_EVENT_INDEX, bool full_← redraw=true)
12.12.2.16set_text(const_std::string &evcategory, const_std::string &evtimestamp, const_std::string &evname, const_std::string &evdata1) 154
12.12.2.17enqueue_draw()
12.12.2.1&convert_y(int y)
12.12.2.19draw_event(editable_events::iterator ei, int index)
12.12.2.20draw_events()
12.12.2.21change_vert()
12.12.2.22page_movement(int new_value)
12.12.2.23page_topper(editable_events::iterator newcurrent)
12.12.2.24decrement_top()
12.12.2.25ncrement_top()
12.12.2.26decrement_current()
12.12.2.27increment_current()
12.12.2.2&decrement_bottom()
12.12.2.29ncrement_bottom()
12.12.2.30on_realize()
12.12.2.31on_expose_event(GdkEventExpose *ev)
12.12.2.32on_button_press_event(GdkEventButton *ev)
12.12.2.33on_button_release_event(GdkEventButton *ev)
12.12.2.34on_focus_in_event(GdkEventFocus *ev)
12.12.2.35on_focus_out_event(GdkEventFocus *ev)
12.12.2.36on_scroll_event(GdkEventScroll *ev)
12.12.2.37on_size_allocate(Gtk::Allocation &)
12.12.2.3&on_move_up()
12.12.2.39on_move_down()
12.12.2.40on_frame_up()
12.12.2.41on_frame_down()
12.12.2.42on_frame_home()
12.12.2.43on_frame_end()

xxvi CONTENTS

12.12.3 Friends And Related Function Documentation	158
12.12.3.1 eventedit	158
12.12.4 Field Documentation	158
12.12.4.1 m_parent	158
12.12.4.2 m_seq	158
12.12.4.3 m_event_container	158
12.12.4.4 m_slots_chars	158
12.12.4.5 m_char_w	159
12.12.4.6 m_setbox_w	159
12.12.4.7 m_slots_x	159
12.12.4.8 m_slots_y	159
12.12.4.9 m_event_count	159
12.12.4.10m_line_count	159
12.12.4.11m_line_maximum	159
12.12.4.12m_line_overlap	159
12.12.4.13m_top_index	159
12.12.4.14m_current_index	159
12.12.4.15m_top_iterator	159
12.12.4.16m_bottom_iterator	159
12.12.4.17m_current_iterator	159
12.12.4.18m_pager_index	159
12.13seq64::font Class Reference	159
12.13.1 Member Enumeration Documentation	161
12.13.1.1 Color	161
12.13.2 Constructor & Destructor Documentation	161
12.13.2.1 font()	161
12.13.3 Member Function Documentation	161
12.13.3.1 init(Glib::RefPtr< Gdk::Window > windo)	161
12.13.3.2 render_string_on_drawable(Glib::RefPtr< Gdk::GC > m_gc, int x, int y, Glib← ::RefPtr< Gdk::Drawable > drawable, const char *str, font::Color col, bool invert=false) const	161

CONTENTS xxvii

12.13.3.3 char_width() const	162
12.13.3.4 char_height() const	162
12.13.3.5 padded_height() const	162
12.13.4 Field Documentation	162
12.13.4.1 m_use_new_font	162
12.13.4.2 m_cell_w	162
12.13.4.3 m_cell_h	162
12.13.4.4 m_font_w	162
12.13.4.5 m_font_h	162
12.13.4.6 m_offset	162
12.13.4.7 m_padded_h	162
12.13.4.8 m_pixmap	162
12.13.4.9 m_black_pixmap	162
12.13.4.10m_white_pixmap	163
12.13.4.11m_b_on_y_pixmap	163
12.13.4.12m_y_on_b_pixmap	163
12.13.4.13m_b_on_c_pixmap	163
12.13.4.14m_c_on_b_pixmap	163
12.13.4.15m_clip_mask	163
12.14seq64::FruityPerfInput Class Reference	163
12.14.1 Constructor & Destructor Documentation	165
12.14.1.1 FruityPerfInput()	165
12.14.2 Member Function Documentation	165
12.14.2.1 on_button_press_event(GdkEventButton *ev, perfroll &roll)	165
12.14.2.2 on_button_release_event(GdkEventButton *ev, perfroll &roll)	165
12.14.2.3 on_motion_notify_event(GdkEventMotion *ev, perfroll &roll)	166
12.14.2.4 update_mouse_pointer(perfroll &roll)	166
12.14.2.5 on_left_button_pressed(GdkEventButton *ev, perfroll &roll)	166
12.14.2.6 on_right_button_pressed(GdkEventButton *ev, perfroll &roll)	166
12.14.3 Friends And Related Function Documentation	167

xxviii CONTENTS

12.14.3.1 perfroll	67
12.14.4 Field Documentation	67
12.14.4.1 m_current_x	67
12.14.4.2 m_current_y	67
12.15seq64::FruitySeqEventInput Struct Reference	67
12.15.1 Constructor & Destructor Documentation	68
12.15.1.1 FruitySeqEventInput()	68
12.15.2 Member Function Documentation	68
12.15.2.1 update_mouse_pointer(seqevent &ths)	68
12.15.2.2 on_button_press_event(GdkEventButton *ev, seqevent &ths)	69
12.15.2.3 on_button_release_event(GdkEventButton *ev, seqevent &ths) 16	69
12.15.2.4 on_motion_notify_event(GdkEventMotion *ev, seqevent &ths)	70
12.15.3 Field Documentation	70
12.15.3.1 m_justselected_one	70
12.15.3.2 m_is_drag_pasting_start	70
12.15.3.3 m_is_drag_pasting	70
12.16seq64::FruitySeqRollInput Class Reference	70
12.16.1 Constructor & Destructor Documentation	71
12.16.1.1 FruitySeqRollInput()	71
12.16.2 Member Function Documentation	71
12.16.2.1 update_mouse_pointer(seqroll &ths)	71
12.16.2.2 on_button_press_event(GdkEventButton *ev, seqroll &ths)	71
12.16.2.3 on_button_release_event(GdkEventButton *ev, seqroll &ths)	71
12.16.2.4 on_motion_notify_event(GdkEventMotion *ev, seqroll &ths) 17	71
12.16.3 Field Documentation	72
12.16.3.1 m_erase_painting	72
12.16.3.2 m_drag_paste_start_pos	72
12.17seq64::gui_assistant Class Reference	72
12.17.1 Detailed Description	73
12.17.2 Constructor & Destructor Documentation	73

CONTENTS xxix

12.17.2.1 gui_assistant(keys_perform &kp)	173
12.17.2.2 ~gui_assistant()	173
12.17.3 Member Function Documentation	173
12.17.3.1 quit()=0	173
12.17.3.2 jack_idle_connect(jack_assistant &jack)=0	173
12.17.3.3 lash_timeout_connect(lash *lashobject)=0	174
12.17.3.4 keys() const	174
12.17.3.5 keys()	174
12.17.4 Field Documentation	174
12.17.4.1 m_keys_perform	174
12.18seq64::gui_assistant_gtk2 Class Reference	174
12.18.1 Constructor & Destructor Documentation	175
12.18.1.1 gui_assistant_gtk2()	175
12.18.1.2 ~gui_assistant_gtk2()	175
12.18.2 Member Function Documentation	175
12.18.2.1 quit()	175
12.18.2.2 lash_timeout_connect(lash *lashobject)	175
12.18.2.3 jack_idle_connect(jack_assistant &jack)	175
12.18.3 Field Documentation	176
12.18.3.1 sm_internal_keys	176
12.19seq64::gui_drawingarea_gtk2 Class Reference	176
12.19.1 Detailed Description	179
12.19.2 Constructor & Destructor Documentation	179
12.19.2.1 gui_drawingarea_gtk2(const gui_drawingarea_gtk2 &)	179
12.19.2.2 gui_drawingarea_gtk2(perform &p, int window_x=0, int window_y=0)	179
12.19.2.3 gui_drawingarea_gtk2(perform &a_perf, Gtk::Adjustment &a_hadjust, Gtk:: Adjustment &a_vadjust, int window_x=0, int window_y=0)	179
12.19.2.4 ~gui_drawingarea_gtk2()	179
12.19.3 Member Function Documentation	179
12.19.3.1 operator=(const gui_drawingarea_gtk2 &)	179
12.19.3.2 window_x() const	179

CONTENTS

12.19.3.3 window_y() const	180
12.19.3.4 current_x() const	180
12.19.3.5 current_y() const	180
12.19.3.6 drop_x() const	180
12.19.3.7 drop_y() const	180
12.19.3.8 force_draw()	180
12.19.3.9 perf()	180
12.19.3.10clear_window()	180
12.19.3.11set_line(Gdk::LineStyle Is, int width=1)	180
12.19.3.12draw_line(int x1, int y1, int x2, int y2)	180
12.19.3.13draw_line(const Color &c, int x1, int y1, int x2, int y2)	180
12.19.3.14draw_line_on_pixmap(int x1, int y1, int x2, int y2)	181
12.19.3.15draw_line_on_pixmap(const Color &c, int x1, int y1, int x2, int y2)	181
12.19.3.16draw_line(Glib::RefPtr< Gdk::Pixmap > &pixmap, int x1, int y1, int x2, int y2)	181
12.19.3.17draw_line(Glib::RefPtr< Gdk::Pixmap > &pixmap, const Color &c, int x1, int y1, int x2, int y2)	181
12.19.3.18draw_line(Glib::RefPtr< Gdk::Drawable > &drawable, int x1, int y1, int x2, int y2)	182
12.19.3.19draw_line(Glib::RefPtr< Gdk::Drawable > &drawable, const Color &c, int x1, int y1, int x2, int y2)	182
12.19.3.20render_string(int x, int y, const std::string &s, font::Color color, bool invert=false) .	182
12.19.3.21render_string_on_pixmap(int x, int y, const std::string &s, font::Color color, bool invert=false)	182
12.19.3.22draw_rectangle(int x, int y, int lx, int ly, bool fill=true)	183
12.19.3.23draw_rectangle(const Color &c, int x, int y, int lx, int ly, bool fill=true)	183
12.19.3.24draw_rectangle(Glib::RefPtr< Gdk::Drawable > &drawable, int x, int y, int lx, int ly, bool fill=true)	183
12.19.3.25draw_rectangle(Glib::RefPtr< Gdk::Drawable > &drawable, const Color &c, int x, int y, int lx, int ly, bool fill=true)	184
12.19.3.26draw_rectangle(Glib::RefPtr< Gdk::Pixmap > &pixmap, int x, int y, int lx, int ly, bool fill=true)	184
12.19.3.27draw_rectangle(Glib::RefPtr< Gdk::Pixmap > &pixmap, const Color &c, int x, int y, int lx, int ly, bool fill=true)	184
12.19.3.28draw_rectangle_on_pixmap(int x, int y, int lx, int ly, bool fill=true)	185

CONTENTS xxxi

12.19.3.29draw_rectangle_on_pixmap(const Color &c, int x, int y, int lx, int ly, bool fill=true)	185
12.19.3.30draw_normal_rectangle_on_pixmap(int x, int y, int lx, int ly, bool fill=true)	185
12.19.3.31draw_drawable(int xsrc, int ysrc, int xdest, int ydest, int width, int height)	185
12.19.3.32scroll_hadjust(Gtk::Adjustment &hadjust, double step)	185
12.19.3.33scroll_vadjust(Gtk::Adjustment &vadjust, double step)	186
12.19.3.34scroll_hset(Gtk::Adjustment &hadjust, double value)	186
12.19.3.35scroll_vset(Gtk::Adjustment &vadjust, double value)	186
12.19.3.36set_current_drop_x(int x)	186
12.19.3.37set_current_drop_y(int y)	186
12.19.3.38gtk_drawarea_init()	186
12.19.3.39on_realize()	186
12.19.4 Field Documentation	186
12.19.4.1 m_gc	186
12.19.4.2 m_window	186
12.19.4.3 m_vadjust	187
12.19.4.4 m_hadjust	187
12.19.4.5 m_pixmap	187
12.19.4.6 m_background	187
12.19.4.7 m_foreground	187
12.19.4.8 m_mainperf	187
12.19.4.9 m_window_x	187
12.19.4.10m_window_y	187
12.19.4.11m_current_x	187
12.19.4.12m_current_y	187
12.19.4.13m_drop_x	187
12.19.4.14m_drop_y	188
12.20seq64::gui_palette_gtk2 Class Reference	188
12.20.1 Detailed Description	191
12.20.2 Member Typedef Documentation	191
12.20.2.1 Color	191

xxxii CONTENTS

12.20.3 Constructor & Destructor Documentation	192
12.20.3.1 gui_palette_gtk2()	192
12.20.3.2 ~gui_palette_gtk2()	192
12.20.4 Member Function Documentation	192
12.20.4.1 load_inverse_palette(bool inverse=true)	192
12.20.4.2 is_inverse()	192
12.20.4.3 line_color() const	192
12.20.4.4 progress_color() const	192
12.20.4.5 black() const	192
12.20.4.6 dark_red() const	192
12.20.4.7 dark_green() const	192
12.20.4.8 dark_orange() const	192
12.20.4.9 dark_blue() const	192
12.20.4.10dark_magenta() const	192
12.20.4.11dark_cyan() const	192
12.20.4.12white() const	193
12.20.4.13grey() const	193
12.20.4.14dark_grey() const	193
12.20.4.15ight_grey() const	193
12.20.4.16red() const	193
12.20.4.17orange() const	193
12.20.4.18yellow() const	193
12.20.4.19green() const	193
12.20.4.20blue() const	193
12.20.4.21black_paint() const	193
12.20.4.22white_paint() const	193
12.20.4.23black_key() const	193
12.20.4.24white_key() const	193
12.20.4.25bg_color() const	193
12.20.4.26bg_color(const Color &c)	193

CONTENTS xxxiii

12.20.4.27fg_color() const	193
12.20.4.28fg_color(const Color &c)	193
12.20.5 Field Documentation	193
12.20.5.1 m_is_inverse	193
12.20.5.2 m_black	194
12.20.5.3 m_dk_red	194
12.20.5.4 m_dk_green	194
12.20.5.5 m_dk_orange	194
12.20.5.6 m_dk_blue	194
12.20.5.7 m_dk_magenta	194
12.20.5.8 m_dk_cyan	194
12.20.5.9 m_red	194
12.20.5.10m_white	194
12.20.5.11m_orange	194
12.20.5.12m_yellow	194
12.20.5.13m_green	194
12.20.5.14m_blue	194
12.20.5.15m_grey	194
12.20.5.16m_dk_grey	194
12.20.5.17m_lt_grey	194
12.20.5.18m_blk_paint	194
12.20.5.19m_wht_paint	194
12.20.5.20m_blk_key	194
12.20.5.21m_wht_key	194
12.20.5.22m_line_color	194
12.20.5.23m_progress_color	194
12.20.5.24m_bg_color	194
12.20.5.25m_fg_color	195
12.21seq64::gui_window_gtk2 Class Reference	195
12.21.1 Constructor & Destructor Documentation	196

CONTENTS

196
196
197
197
197
197
197
197
197
197
197
197
198
198
198
198
198
198
198
201
201
201
201
201 201
201
201 201
201 201 202

CONTENTS XXXV

12.22.2.7 get_beats_per_measure() const	02
12.22.2.8 set_beats_per_measure(int bpm)	02
12.22.2.9 get_beats_per_minute() const	02
12.22.2.10set_beats_per_minute(int bpminute)	02
12.22.2.11transport_state() const	02
12.22.2.12nit()	02
12.22.2.13deinit()	03
12.22.2.14session_event()	03
12.22.2.15start()	03
12.22.2.16stop()	04
12.22.2.17position(bool to_left_tick, bool relocate=false)	04
12.22.2.1&output(jack_scratchpad &pad)	05
12.22.2.19set_ppqn(int ppqn)	05
12.22.2.20get_jack_tick() const	06
12.22.2.21get_jack_pos() const	06
12.22.2.22client() const	06
12.22.2.23client_name() const	06
12.22.2.24client_uuid() const	:06
12.22.2.25set_jack_running(bool flag)	06
12.22.2.2@tick_multiplier() const	:06
12.22.2.27info_message(const std::string &msg)	:06
12.22.2.2&error_message(const std::string &msg)	:06
12.22.2.2client_open(const std::string &clientname)	07
12.22.2.30get_jack_client_info()	:07
12.22.2.31show_statuses(unsigned bits)	:07
12.22.2.3&how_position(const jack_position_t &pos) const	:08
12.22.2.33sync(jack_transport_state_t state=(jack_transport_state_t)(-1))	:09
12.22.2.34set_position(midipulse currenttick)	:09
12.22.3 Friends And Related Function Documentation	10
12.22.3.1 jack_process_callback	10

xxxvi CONTENTS

12.22.3.2 jack_shutdown_callback	210
12.22.3.3 jack_sync_callback	210
12.22.3.4 jack_timebase_callback	210
12.22.3.5 get_current_jack_position	211
12.22.3.6 jack_session_callback	211
12.22.4 Field Documentation	212
12.22.4.1 sm_status_pairs	212
12.22.4.2 m_jack_parent	212
12.22.4.3 m_jack_client	212
12.22.4.4 m_jack_client_name	212
12.22.4.5 m_jack_client_uuid	212
12.22.4.6 m_jack_frame_current	212
12.22.4.7 m_jack_frame_last	212
12.22.4.8 m_jack_pos	212
12.22.4.9 m_jack_transport_state	212
12.22.4.10m_jack_transport_state_last	212
12.22.4.11m_jack_tick	212
12.22.4.12m_jsession_ev	212
12.22.4.13m_jack_running	213
12.22.4.14m_jack_master	213
12.22.4.15m_ppqn	213
12.22.4.16m_beats_per_measure	213
12.22.4.17m_beat_width	213
12.22.4.18m_beats_per_minute	213
12.23seq64::jack_scratchpad Class Reference	213
12.23.1 Detailed Description	213
12.23.2 Field Documentation	214
12.23.2.1 js_current_tick	214
12.23.2.2 js_total_tick	214
12.23.2.3 js_clock_tick	214

CONTENTS xxxvii

12.23.2.4 js_jack_stopped	214
12.23.2.5 js_dumping	214
12.23.2.6 js_init_clock	214
12.23.2.7 js_looping	214
12.23.2.8 js_playback_mode	214
12.23.2.9 js_ticks_converted_last	214
12.24seq64::jack_status_pair_t Struct Reference	214
12.24.1 Field Documentation	214
12.24.1.1 jf_bit	214
12.24.1.2 jf_meaning	214
12.25seq64::keybindentry Class Reference	214
12.25.1 Member Enumeration Documentation	215
12.25.1.1 type	215
12.25.2 Constructor & Destructor Documentation	215
12.25.2.1 keybindentry(type t, unsigned int *location_to_write=nullptr, perform *p=nullptr, long s=0)	215
12.25.3 Member Function Documentation	216
12.25.3 Member Function Documentation	
	216
12.25.3.1 set(unsigned int val)	216 216
12.25.3.1 set(unsigned int val)	216 216 216
12.25.3.1 set(unsigned int val)	216 216 216 216
12.25.3.1 set(unsigned int val)	216 216 216 216 216
12.25.3.1 set(unsigned int val)	216 216 216 216 216 216
12.25.3.1 set(unsigned int val)	216 216 216 216 216 216 216
12.25.3.1 set(unsigned int val) 12.25.3.2 on_key_press_event(GdkEventKey *event) 12.25.4 Friends And Related Function Documentation 12.25.4.1 options 12.25.5 Field Documentation 12.25.5.1 m_key 12.25.5.2 m_type	216 216 216 216 216 216 216 216
12.25.3.1 set(unsigned int val) 12.25.3.2 on_key_press_event(GdkEventKey *event) 12.25.4 Friends And Related Function Documentation 12.25.4.1 options 12.25.5 Field Documentation 12.25.5.1 m_key 12.25.5.2 m_type 12.25.5.3 m_perf	216 216 216 216 216 216 216 216 216
12.25.3.1 set(unsigned int val) 12.25.3.2 on_key_press_event(GdkEventKey *event) 12.25.4 Friends And Related Function Documentation 12.25.4.1 options 12.25.5 Field Documentation 12.25.5.1 m_key 12.25.5.2 m_type 12.25.5.3 m_perf 12.25.5.4 m_slot	216 216 216 216 216 216 216 216 217
12.25.3.1 set(unsigned int val) 12.25.3.2 on_key_press_event(GdkEventKey *event) 12.25.4 Friends And Related Function Documentation 12.25.4.1 options 12.25.5 Field Documentation 12.25.5.1 m_key 12.25.5.2 m_type 12.25.5.3 m_perf 12.25.5.4 m_slot 12.26seq64::keys_perform Class Reference	216 216 216 216 216 216 216 217 222
12.25.3.1 set(unsigned int val) 12.25.3.2 on_key_press_event(GdkEventKey *event) 12.25.4 Friends And Related Function Documentation 12.25.4.1 options 12.25.5 Field Documentation 12.25.5.1 m_key 12.25.5.2 m_type 12.25.5.3 m_perf 12.25.5.4 m_slot 12.26seq64::keys_perform Class Reference 12.26.1 Detailed Description	216 216 216 216 216 216 216 217 222 222

xxxviii CONTENTS

12.26.3 Constructor & Destructor Documentation	222
12.26.3.1 keys_perform()	222
12.26.3.2 ~keys_perform()	222
12.26.4 Member Function Documentation	222
12.26.4.1 set_keys(const keys_perform_transfer &kpt)	222
12.26.4.2 get_keys(keys_perform_transfer &kpt)	223
12.26.4.3 bpm_up() const	223
12.26.4.4 bpm_up(unsigned int x)	223
12.26.4.5 bpm_dn() const	223
12.26.4.6 bpm_dn(unsigned int x)	223
12.26.4.7 replace() const	223
12.26.4.8 replace(unsigned int x)	223
12.26.4.9 queue() const	223
12.26.4.10queue(unsigned int x)	223
12.26.4.11keep_queue() const	224
12.26.4.12keep_queue(unsigned int x)	224
12.26.4.13snapshot_1() const	224
12.26.4.14snapshot_1(unsigned int x)	224
12.26.4.15snapshot_2() const	224
12.26.4.16snapshot_2(unsigned int x)	224
12.26.4.17screenset_up() const	224
12.26.4.18screenset_up(unsigned int x)	224
12.26.4.1%creenset_dn() const	224
12.26.4.20screenset_dn(unsigned int x)	224
12.26.4.21set_playing_screenset() const	224
12.26.4.22set_playing_screenset(unsigned int x)	224
12.26.4.23group_on() const	225
12.26.4.24group_on(unsigned int x)	225
12.26.4.25group_off() const	225
12.26.4.26group_off(unsigned int x)	225

CONTENTS xxxix

12.26.4.27group_learn() const
12.26.4.2&group_learn(unsigned int x)
12.26.4.29start() const
12.26.4.30start(unsigned int x)
12.26.4.31pause() const
12.26.4.32pause(unsigned int x)
12.26.4.33pattern_edit() const
12.26.4.34pattern_edit(unsigned int x)
12.26.4.35event_edit() const
12.26.4.36event_edit(unsigned int x)
12.26.4.37stop() const
12.26.4.38stop(unsigned int x)
12.26.4.39show_ui_sequence_key() const
12.26.4.40show_ui_sequence_key(bool flag)
12.26.4.41show_ui_sequence_number() const
12.26.4.42show_ui_sequence_number(bool flag)
12.26.4.43get_key_events()
12.26.4.44get_key_groups()
12.26.4.45get_key_events_rev()
12.26.4.46get_key_groups_rev()
12.26.4.47lookup_keyevent_key(long seqnum)
12.26.4.48ookup_keyevent_seq(unsigned int keycode)
12.26.4.49ookup_keygroup_key(long groupnum)
12.26.4.50ookup_keygroup_group(unsigned int keycode)
12.26.4.51key_name(unsigned int key) const
12.26.4.52set_all_key_events()
12.26.4.53set_all_key_groups()
12.26.4.54set_key_event(unsigned int keycode, long sequence_slot)
12.26.4.55set_key_group(unsigned int keycode, long group_slot)
12.26.4.56at_bpm_up()

xI CONTENTS

8
9
9
9
9
9
9
9
9
9
9
0
0
0
0
0
0
0
0
0
0
0
0
0
0
0
1
1
1
1

CONTENTS xli

12.26.6.7 m_key_bpm_up	.31
12.26.6.8 m_key_bpm_dn	:31
12.26.6.9 m_key_replace	:31
12.26.6.10m_key_queue	:31
12.26.6.11m_key_keep_queue	:31
12.26.6.12m_key_snapshot_1	:31
12.26.6.13m_key_snapshot_2	:31
12.26.6.14m_key_screenset_up	:31
12.26.6.15m_key_screenset_dn	:31
12.26.6.16m_key_set_playing_screenset	:31
12.26.6.17m_key_group_on	:31
12.26.6.18m_key_group_off	:32
12.26.6.19m_key_group_learn	:32
12.26.6.20m_key_start	:32
12.26.6.21m_key_pause	:32
12.26.6.22m_key_pattern_edit	:32
12.26.6.23m_key_event_edit	:32
12.26.6.24m_key_stop	:32
12.27seq64::keys_perform_gtk2 Class Reference	:32
12.27.1 Detailed Description	:34
12.27.2 Constructor & Destructor Documentation	:34
12.27.2.1 keys_perform_gtk2()	:34
12.27.2.2 ~keys_perform_gtk2()	:34
12.27.3 Member Function Documentation	:34
12.27.3.1 key_name(unsigned int key) const	:34
12.27.3.2 set_all_key_events()	:34
12.27.3.3 set_all_key_groups()	:34
12.28seq64::keys_perform_transfer Struct Reference	:34
12.28.1 Field Documentation	:35
12.28.1.1 kpt_bpm_up	:35

XIII CONTENTS

12.28.1.2 kpt_bpm_dn	. 235
12.28.1.3 kpt_screenset_up	. 235
12.28.1.4 kpt_screenset_dn	. 235
12.28.1.5 kpt_set_playing_screenset	. 235
12.28.1.6 kpt_group_on	. 235
12.28.1.7 kpt_group_off	. 235
12.28.1.8 kpt_group_learn	. 235
12.28.1.9 kpt_replace	. 235
12.28.1.10kpt_queue	. 235
12.28.1.11kpt_keep_queue	. 235
12.28.1.12kpt_snapshot_1	. 235
12.28.1.13kpt_snapshot_2	. 236
12.28.1.14kpt_start	. 236
12.28.1.15kpt_stop	. 236
12.28.1.16kpt_show_ui_sequence_key	. 236
12.28.1.17kpt_show_ui_sequence_number	. 236
12.28.1.18kpt_pattern_edit	. 236
12.28.1.19kpt_event_edit	. 236
12.28.1.20kpt_pause	. 236
12.29seq64::keystroke Class Reference	. 236
12.29.1 Detailed Description	. 237
12.29.2 Constructor & Destructor Documentation	. 237
12.29.2.1 keystroke()	. 237
12.29.2.2 keystroke(unsigned int key, bool press=SEQ64_KEYSTROKE_PRESS, in modkey=int(SEQ64_NO_MASK))	
12.29.2.3 keystroke(const keystroke &rhs)	. 237
12.29.3 Member Function Documentation	. 237
12.29.3.1 operator=(const keystroke &rhs)	. 237
12.29.3.2 is_press() const	. 238
12.29.3.3 is_letter(unsigned int ch=SEQ64_KEYSTROKE_BAD_VALUE) const	. 238
12.29.3.4 is(unsigned int ch) const	. 238

CONTENTS xliii

12.29.3.5 is_delete() const	38
12.29.3.6 key() const	38
12.29.3.7 shift_lock()	38
12.29.3.8 modifier() const	39
12.29.3.9 mod_control() const	39
12.29.3.10mod_control_shift() const	39
12.29.3.11mod_super() const	39
12.29.4 Field Documentation	39
12.29.4.1 m_is_press	39
12.29.4.2 m_key	39
12.29.4.3 m_modifier	39
12.30seq64::lash Class Reference	39
12.30.1 Detailed Description	10
12.30.2 Constructor & Destructor Documentation	10
12.30.2.1 lash(perform &p, int argc, char **argv)	10
12.30.3 Member Function Documentation	10
12.30.3.1 set_alsa_client_id(int id)	10
12.30.3.2 start()	10
12.30.3.3 process_events()	10
12.30.3.4 init()	11
12.30.3.5 handle_event(lash_event_t *conf)	11
12.30.3.6 handle_config(lash_config_t *conf)	11
12.30.4 Field Documentation	11
12.30.4.1 m_perform	11
12.30.4.2 m_client	11
12.30.4.3 m_lash_args	11
12.30.4.4 m_is_lash_supported	11
12.31 seq64::Ifownd Class Reference	11
12.31.1 Detailed Description	13
12.31.2 Constructor & Destructor Documentation	13

XIIV CONTENTS

12.31.2.1 Ifownd(perform &p, sequence &seq, seqdata &sdata)	-3
12.31.2.2 ~lfownd()	13
12.31.3 Member Function Documentation	13
12.31.3.1 toggle_visible()	13
12.31.3.2 scale_lfo_change()	13
12.31.3.3 on_focus_out_event(GdkEventFocus *p0)	13
12.31.4 Field Documentation	13
12.31.4.1 m_seq	14
12.31.4.2 m_seqdata	14
12.31.4.3 m_hbox	14
12.31.4.4 m_scale_value	14
12.31.4.5 m_scale_range	14
12.31.4.6 m_scale_speed	14
12.31.4.7 m_scale_phase	14
12.31.4.8 m_scale_wave	14
12.31.4.9 m_value	14
12.31.4.10m_range	14
12.31.4.11m_speed	14
12.31.4.12m_phase	14
12.31.4.13m_wave	14
12.32seq64::maintime Class Reference	14
12.32.1 Detailed Description	16
12.32.2 Constructor & Destructor Documentation	17
12.32.2.1 maintime(const maintime &)	17
12.32.2.2 maintime(perform &p, int ppqn=SEQ64_USE_DEFAULT_PPQN) 24	17
12.32.2.3 ~maintime()	١7
12.32.3 Member Function Documentation	1 7
12.32.3.1 operator=(const maintime &)	17
12.32.3.2 idle_progress(midipulse ticks)	17
12.32.3.3 on_realize()	17

CONTENTS xlv

12.32.3.4 on_expose_event(GdkEventExpose *ev)	247
12.32.4 Friends And Related Function Documentation	247
12.32.4.1 mainwnd	247
12.32.5 Field Documentation	247
12.32.5.1 m_beat_width	247
12.32.5.2 m_bar_width	248
12.32.5.3 m_pill_width	248
12.32.5.4 m_box_width	248
12.32.5.5 m_box_height	248
12.32.5.6 m_flash_width	248
12.32.5.7 m_flash_height	248
12.32.5.8 m_flash_x	248
12.32.5.9 m_box_less_pill	248
12.32.5.10m_tick	248
12.32.5.11m_ppqn	248
12.33seq64::mainwid Class Reference	249
12.33.1 Detailed Description	252
12.33.2 Constructor & Destructor Documentation	252
12.33.2.1 mainwid(perform &p)	252
12.33.2.2 ~mainwid()	252
12.33.3 Member Function Documentation	252
12.33.3.1 set_screenset(int ss, bool setperf=false)	252
12.33.3.2 reset()	253
12.33.3.3 update_sequences_on_window()	253
12.33.3.4 draw_pixmap_on_window()	253
12.33.3.5 fill_background_window()	253
12.33.3.6 redraw(int seq)	253
12.33.3.7 seq_set_and_edit(int seqnum)	253
12.33.3.8 seq_set_and_eventedit(int seqnum)	253
12.33.3.9 draw_marker_on_sequence(int seq, int tick)	253

XIVI CONTENTS

12.33.3.1@pdate_markers(int ticks)	254
12.33.3.11valid_sequence(int seq)	254
12.33.3.12draw_sequence_on_pixmap(int seq)	254
12.33.3.13draw_sequences_on_pixmap()	254
12.33.3.14draw_sequence_pixmap_on_window(int seq)	255
12.33.3.15seq_from_xy(int x, int y)	255
12.33.3.16timeout()	255
12.33.3.17calculate_base_sizes(int seq, int &basex, int &basey)	255
12.33.3.18select_fg_bg_colors(int seqnum)	255
12.33.3.19on_realize()	255
12.33.3.20on_expose_event(GdkEventExpose *ev)	256
12.33.3.21on_button_press_event(GdkEventButton *ev)	256
12.33.3.22on_button_release_event(GdkEventButton *ev)	256
12.33.3.23on_motion_notify_event(GdkEventMotion *p0)	257
12.33.3.24on_focus_in_event(GdkEventFocus *)	257
12.33.3.25on_focus_out_event(GdkEventFocus *)	257
12.33.4 Friends And Related Function Documentation	257
12.33.4.1 mainwnd	257
12.33.4.2 update_mainwid_sequences	257
12.33.5 Field Documentation	258
12.33.5.1 m_moving_seq	258
12.33.5.2 m_button_down	258
12.33.5.3 m_moving	258
12.33.5.4 m_old_seq	258
12.33.5.5 m_screenset	258
12.33.5.6 m_last_tick_x	258
12.33.5.7 m_mainwnd_rows	258
12.33.5.8 m_mainwnd_cols	258
12.33.5.9 m_seqarea_x	258
12.33.5.10m_seqarea_y	258

CONTENTS xlvii

12.33.5.11m_seqarea_seq_x	. 258
12.33.5.12m_seqarea_seq_y	. 258
12.33.5.13m_mainwid_x	. 258
12.33.5.14m_mainwid_y	. 258
12.33.5.15m_mainwid_border	. 258
12.33.5.16m_mainwid_spacing	. 258
12.33.5.17m_text_size_x	. 258
12.33.5.18m_text_size_y	. 258
12.33.5.19m_max_sets	. 258
12.33.5.20m_screenset_slots	. 258
12.33.5.21m_screenset_offset	. 259
12.33.5.22m_progress_height	. 259
12.34seq64::mainwnd Class Reference	. 259
12.34.1 Constructor & Destructor Documentation	. 264
12.34.1.1 mainwnd(perform &p, bool allowperf2=true, int ppqn=SEQ64_USE_DEFAULT PPQN)	
12.34.1.2 ~mainwnd()	. 264
12.34.2 Member Function Documentation	. 264
12.34.2.1 open_file(const std::string &filename)	. 265
12.34.2.2 ppqn() const	. 265
12.34.2.3 ppqn(int ppqn)	. 265
12.34.2.4 handle_signal(int sig)	. 265
12.34.2.5 adj_callback_ss()	. 265
12.34.2.6 adj_callback_bpm()	. 265
12.34.2.7 edit_callback_notepad()	. 265
12.34.2.8 timer_callback()	. 265
12.34.2.9 set_image(bool isrunning)	. 265
12.34.2.10start_playing()	. 266
12.34.2.11pause_playing()	. 266
12.34.2.12stop_playing()	
	. 266

xlviii CONTENTS

1	12.34.2.14earn_toggle()	266
1	12.34.2.15open_performance_edit()	266
1	12.34.2.16open_performance_edit_2()	267
1	12.34.2.17enregister_perfedits()	267
1	12.34.2.18sequence_key(int seq)	267
1	12.34.2.19update_window_title()	267
1	12.34.2.20toLower(std::string &)	267
1	12.34.2.21file_new()	267
1	12.34.2.22ile_open()	267
1	12.34.2.23file_save()	267
1	12.34.2.24set_song_mute(perform::mute_op_t op)	267
1	12.34.2.25ile_import_dialog()	267
1	12.34.2.26options_dialog()	267
1	12.34.2.27about_dialog()	267
1	12.34.2.2&query_save_changes()	268
1	12.34.2.29new_open_error_dialog()	268
1	12.34.2.30file_save_as(bool do_export=false)	268
1	12.34.2.31file_exit()	268
1	12.34.2.32new_file()	268
1	12.34.2.33save_file()	269
1	12.34.2.34choose_file()	269
1	12.34.2.35s_save()	269
1	12.34.2.36nstall_signal_handlers()	269
1	12.34.2.37signal_action(Glib::IOCondition condition)	269
1	12.34.2.3&n_delete_event(GdkEventAny *ev)	269
1	12.34.2.39on_key_press_event(GdkEventKey *ev)	269
1	12.34.2.40on_key_release_event(GdkEventKey *ev)	269
1	12.34.2.41on_grouplearnchange(bool state)	269
12.34.3 F	Field Documentation	270
1	12.34.3.1 m_sigpipe	270

CONTENTS xlix

12.34.3.2 m_tooltips
12.34.3.3 m_menubar
12.34.3.4 m_menu_file
12.34.3.5 m_menu_edit
12.34.3.6 m_menu_view
12.34.3.7 m_menu_help
12.34.3.8 m_ppqn
12.34.3.9 m_main_wid
12.34.3.10m_main_time
12.34.3.11m_perf_edit
12.34.3.12m_perf_edit_2
12.34.3.13m_options
12.34.3.14m_main_cursor
12.34.3.15m_image_play
12.34.3.16m_button_learn
12.34.3.17m_button_stop
12.34.3.18m_button_play
12.34.3.19m_button_perfedit
12.34.3.20m_adjust_bpm
12.34.3.21m_spinbutton_bpm
12.34.3.22m_adjust_ss
12.34.3.23m_spinbutton_ss
12.34.3.24m_adjust_load_offset
12.34.3.25m_spinbutton_load_offset
12.34.3.26m_entry_notes
12.34.3.27m_is_running
12.34.3.28m_timeout_connect
12.34.3.29m_menu_mode
12.34.3.30m_call_seq_edit
12.34.3.31m_call_seq_eventedit

I CONTENTS

12.35seq64::mastermidibus Class Reference	272
12.35.1 Constructor & Destructor Documentation	275
12.35.1.1 mastermidibus(int ppqn=SEQ64_USE_DEFAULT_PPQN, int bpm=c_beats_← per_minute)	275
12.35.1.2 ~mastermidibus()	276
12.35.2 Member Function Documentation	276
12.35.2.1 init(int ppqn)	276
12.35.2.2 get_alsa_seq() const	276
12.35.2.3 get_num_out_buses() const	276
12.35.2.4 get_num_in_buses() const	276
12.35.2.5 set_beats_per_minute(int bpm)	276
12.35.2.6 set_ppqn(int ppqn)	277
12.35.2.7 filter_by_channel() const	277
12.35.2.8 filter_by_channel(bool flag)	277
12.35.2.9 get_beats_per_minute() const	277
12.35.2.10get_ppqn() const	277
12.35.2.11get_midi_out_bus_name(int bus)	277
12.35.2.12get_midi_in_bus_name(int bus)	277
12.35.2.13print()	277
12.35.2.14flush()	277
12.35.2.15start()	278
12.35.2.16stop()	278
12.35.2.17clock(midipulse tick)	278
12.35.2.1&ontinue_from(midipulse tick)	278
12.35.2.19nit_clock(midipulse tick)	278
12.35.2.20poll_for_midi()	278
12.35.2.21is_more_input()	278
12.35.2.22get_midi_event(event *in)	279
12.35.2.23set_sequence_input(bool state, sequence *seq)	279
12.35.2.24dump_midi_input(event in)	279
12.35.2.25s_dumping() const	279

12.35.2.26get_sequence() const	279
12.35.2.27sysex(event *event)	279
12.35.2.2&port_start(int client, int port)	280
12.35.2.29port_exit(int client, int port)	280
12.35.2.30play(bussbyte bus, event *e24, midibyte channel)	280
12.35.2.31set_clock(bussbyte bus, clock_e clock_type)	280
12.35.2.32get_clock(bussbyte bus)	281
12.35.2.33set_input(bussbyte bus, bool inputing)	281
12.35.2.34get_input(bussbyte bus)	281
12.35.3 Field Documentation	281
12.35.3.1 m_alsa_seq	281
12.35.3.2 m_max_busses	281
12.35.3.3 m_num_out_buses	281
12.35.3.4 m_num_in_buses	281
12.35.3.5 m_buses_out	282
12.35.3.6 m_buses_in	282
12.35.3.7 m_bus_announce	282
12.35.3.8 m_buses_out_active	282
12.35.3.9 m_buses_in_active	282
12.35.3.10m_buses_out_init	282
12.35.3.11m_buses_in_init	282
12.35.3.12m_init_clock	282
12.35.3.13m_init_input	282
12.35.3.14m_queue	282
12.35.3.15m_ppqn	282
12.35.3.16m_beats_per_minute	282
12.35.3.17m_num_poll_descriptors	282
12.35.3.18m_poll_descriptors	282
12.35.3.19m_dumping_input	282
12.35.3.20m_vector_sequence	282

lii CONTENTS

12.35.3.21m_filter_by_channel	282
12.35.3.22m_seq	282
12.35.3.23m_mutex	282
12.36seq64::midi_container Class Reference	283
12.36.1 Detailed Description	285
12.36.2 Constructor & Destructor Documentation	285
12.36.2.1 midi_container(sequence &seq)	285
12.36.2.2 ~midi_container()	285
12.36.3 Member Function Documentation	285
12.36.3.1 fill(int tracknumber, const perform &p)	285
12.36.3.2 size() const	286
12.36.3.3 done() const	286
12.36.3.4 put(midibyte b)=0	286
12.36.3.5 get() const =0	286
12.36.3.6 clear()=0	286
12.36.3.7 position_reset() const	286
12.36.3.8 position() const	286
12.36.3.9 position_increment() const	286
12.36.3.10add_variable(midipulse v)	286
12.36.3.11add_long(midipulse x)	287
12.36.3.12add_short(midishort x)	287
12.36.3.13add_event(const event &e, midipulse deltatime)	287
12.36.3.14fill_seq_number(int seq)	287
12.36.3.15fill_seq_name(const std::string &name)	287
12.36.3.16fill_meta_track_end(midipulse deltatime)	288
12.36.3.17fill_proprietary()	288
12.36.3.18fill_time_sig_and_tempo(const perform &p)	288
12.36.3.1%ong_fill_seq_event(const trigger &trig, midipulse prev_timestamp)	288
12.36.3.20song_fill_seq_trigger(const trigger &trig, midipulse len, midipulse prev_timestamp)	288
12.36.4 Friends And Related Function Documentation	289

12.36.4.1 midifile	289
12.36.5 Field Documentation	289
12.36.5.1 m_sequence	289
12.36.5.2 m_position_for_get	289
12.37seq64::midi_control Class Reference	289
12.37.1 Detailed Description	290
12.37.2 Constructor & Destructor Documentation	290
12.37.2.1 midi_control()	290
12.37.3 Member Function Documentation	291
12.37.3.1 active() const	291
12.37.3.2 inverse_active() const	291
12.37.3.3 status() const	291
12.37.3.4 data() const	291
12.37.3.5 min_value() const	291
12.37.3.6 max_value() const	291
12.37.3.7 set(int values[6])	291
12.37.3.8 set(midibyte values[6])	291
12.37.3.9 match(midibyte status, midibyte data) const	291
12.37.3.10n_range(midibyte data) const	291
12.37.4 Field Documentation	291
12.37.4.1 m_active	291
12.37.4.2 m_inverse_active	292
12.37.4.3 m_status	292
12.37.4.4 m_data	292
12.37.4.5 m_min_value	292
12.37.4.6 m_max_value	292
12.38seq64::midi_list Class Reference	292
12.38.1 Member Typedef Documentation	294
12.38.1.1 CharList	294
12.38.2 Constructor & Destructor Documentation	294

liv CONTENTS

12.38.2.1 midi_list(sequence &seq)	294
12.38.2.2 ~midi_list()	294
12.38.3 Member Function Documentation	294
12.38.3.1 size() const	294
12.38.3.2 done() const	295
12.38.3.3 put(midibyte b)	295
12.38.3.4 get() const	295
12.38.3.5 clear()	295
12.38.4 Field Documentation	295
12.38.4.1 m_char_list	295
12.39seq64::midi_measures Class Reference	295
12.39.1 Detailed Description	296
12.39.2 Constructor & Destructor Documentation	296
12.39.2.1 midi_measures()	296
12.39.2.2 midi_measures(int measures, int beats, int divisions)	296
12.39.3 Member Function Documentation	296
12.39.3.1 measures() const	296
12.39.3.2 measures(int m)	296
12.39.3.3 beats() const	296
12.39.3.4 beats(int b)	296
12.39.3.5 divisions() const	296
12.39.3.6 divisions(int d)	297
12.39.4 Field Documentation	297
12.39.4.1 m_measures	297
12.39.4.2 m_beats	297
12.39.4.3 m_divisions	297
12.40seq64::midi_splitter Class Reference	297
12.40.1 Detailed Description	298
12.40.2 Constructor & Destructor Documentation	298
12.40.2.1 midi_splitter(int ppqn=SEQ64_USE_DEFAULT_PPQN)	298

12.40.2.2 ~midi_splitter()	298
12.40.3 Member Function Documentation	298
12.40.3.1 log_main_sequence(sequence &seq, int seqnum)	298
12.40.3.2 initialize()	299
12.40.3.3 increment(int channel)	299
12.40.3.4 split(perform &p, int screenset)	299
12.40.3.5 ppqn() const	299
12.40.3.6 count() const	299
12.40.3.7 split_channel(const sequence &main_seq, sequence *seq, int channel) 2	299
12.40.4 Field Documentation	300
12.40.4.1 m_ppqn	300
12.40.4.2 m_use_default_ppqn	300
12.40.4.3 m_smf0_channels_count	300
12.40.4.4 m_smf0_channels	300
12.40.4.5 m_smf0_main_sequence	300
12.40.4.6 m_smf0_seq_number	300
12.41seq64::midi_timing Class Reference	300
12.41.1 Detailed Description	301
12.41.2 Constructor & Destructor Documentation	301
12.41.2.1 midi_timing()	301
12.41.2.2 midi_timing(int bpminute, int bpmeasure, int beatwidth, int ppqn)	301
12.41.3 Member Function Documentation	302
12.41.3.1 beats_per_minute() const	302
12.41.3.2 beats_per_minute(int b)	302
12.41.3.3 beats_per_measure() const	302
12.41.3.4 beats_per_measure(int b)	302
12.41.3.5 beat_width() const	302
12.41.3.6 beat_width(int bw)	302
12.41.3.7 ppqn() const	302
12.41.3.8 ppqn(int p)	302

Ivi CONTENTS

12.41.4 Field Documentation	302
12.41.4.1 m_beats_per_minute	303
12.41.4.2 m_beats_per_measure	303
12.41.4.3 m_beat_width	303
12.41.4.4 m_ppqn	303
12.42seq64::midi_vector Class Reference	303
12.42.1 Member Typedef Documentation	305
12.42.1.1 CharVector	305
12.42.2 Constructor & Destructor Documentation	305
12.42.2.1 midi_vector(sequence &seq)	305
12.42.2.2 ~midi_vector()	305
12.42.3 Member Function Documentation	305
12.42.3.1 size() const	305
12.42.3.2 done() const	306
12.42.3.3 put(midibyte b)	306
12.42.3.4 get() const	306
12.42.3.5 clear()	306
12.42.4 Field Documentation	306
12.42.4.1 m_char_vector	306
12.43seq64::midibus Class Reference	306
12.43.1 Constructor & Destructor Documentation	308
12.43.1.1 midibus(int localclient, int destclient, int destport, snd_seq_t *seq, const char	
*client_name, const char *port_name, int id, int queue, int ppqn=SEQ64_U ← SE_DEFAULT_PPQN)	308
12.43.1.2 midibus(int localclient, snd_seq_t ∗seq, int id, int queue, int ppqn=SEQ64_US↔ E_DEFAULT_PPQN)	309
12.43.1.3 ~midibus()	309
12.43.2 Member Function Documentation	
12.43.2.1 init_out()	
12.43.2.2 init_in()	
12.43.2.3 deinit in()	
12.43.2.4 init_out_sub()	

12.43.2.5 init_in_sub()	10
12.43.2.6 print()	10
12.43.2.7 get_name() const	10
12.43.2.8 get_id() const	10
12.43.2.9 play(event *e24, midibyte channel)	10
12.43.2.10sysex(event *e24)	10
12.43.2.11start()	10
12.43.2.12stop()	10
12.43.2.13clock(midipulse tick)	10
12.43.2.14continue_from(midipulse tick)	10
12.43.2.15nit_clock(midipulse tick)	11
12.43.2.16set_clock(clock_e clocktype)	11
12.43.2.17get_clock() const	11
12.43.2.18set_input(bool inputing)	11
12.43.2.19get_input() const	11
12.43.2.20flush()	11
12.43.2.21get_client() const	11
12.43.2.22get_port() const	11
12.43.2.23set_clock_mod(int clockmod)	11
12.43.2.24get_clock_mod()	11
12.43.3 Friends And Related Function Documentation	11
12.43.3.1 mastermidibus	12
12.43.4 Field Documentation	12
12.43.4.1 m_clock_mod	12
12.43.4.2 m_id	12
12.43.4.3 m_clock_type	12
12.43.4.4 m_inputing	12
12.43.4.5 m_ppqn	12
12.43.4.6 m_seq	12
12.43.4.7 m_dest_addr_client	12

Iviii CONTENTS

12.43.4.8 m_dest_addr_port	312
12.43.4.9 m_local_addr_client	312
12.43.4.10m_local_addr_port	312
12.43.4.11m_queue	312
12.43.4.12m_name	312
12.43.4.13m_lasttick	312
12.43.4.14m_mutex	312
12.44seq64::midifile Class Reference	312
12.44.1 Detailed Description	315
12.44.2 Constructor & Destructor Documentation	315
12.44.2.1 midifile(const std::string &name, int ppqn=SEQ64_USE_DEFAULT_PPQN, bool oldformat=false, bool globalbgs=true)	315
12.44.2.2 ~midifile()	316
12.44.3 Member Function Documentation	316
12.44.3.1 parse(perform &p, int a_screen_set=0)	316
12.44.3.2 write(perform &p)	317
12.44.3.3 write_song(perform &p)	317
12.44.3.4 error_message() const	317
12.44.3.5 error_is_fatal() const	317
12.44.3.6 ppqn() const	317
12.44.3.7 parse_smf_0(perform &p, int screenset)	318
12.44.3.8 parse_smf_1(perform &p, int screenset, bool is_smf0=false)	318
12.44.3.9 parse_prop_header(int file_size)	318
12.44.3.10parse_proprietary_track(perform &a_perf, int file_size)	319
12.44.3.11pow2(int logbase2)	320
12.44.3.12checklen(midilong len, midibyte type)	320
12.44.3.13add_trigger(sequence &seq, midishort ppqn)	320
12.44.3.14read_long()	320
12.44.3.15read_short()	321
12.44.3.16read_byte()	321
12.44.3.17read_varinum()	321

12.44.3.18write_long(midilong value)	321
12.44.3.19write_short(midishort value)	321
12.44.3.20read_byte_array(midibyte *b, int len)	322
12.44.3.21write_byte(midibyte c)	322
12.44.3.22write_varinum(midilong)	322
12.44.3.23write_track_name(const std::string &trackname)	323
12.44.3.24read_track_name()	323
12.44.3.25write_seq_number(midishort seqnum)	323
12.44.3.26read_seq_number()	323
12.44.3.27write_track_end()	324
12.44.3.28write_header(int numtracks)	324
12.44.3.29write_prop_header(midilong tag, long len)	324
12.44.3.30write_proprietary_track(perform &a_perf)	325
12.44.3.31varinum_size(long len) const	325
12.44.3.32prop_item_size(long datalen) const	325
12.44.3.33track_name_size(const std::string &trackname) const	326
12.44.3.34errdump(const std::string &msg)	326
12.44.3.35errdump(const std::string &msg, unsigned long p)	326
12.44.3.36write_track(const midi_vector &lst)	327
12.44.3.37seq_number_size() const	327
12.44.3.3&track_end_size() const	327
12.44.3.39s_sysex_special_id(midibyte ch)	327
12.44.4 Field Documentation	327
12.44.4.1 m_mutex	327
12.44.4.2 m_file_size	327
12.44.4.3 m_error_message	327
12.44.4.4 m_error_is_fatal	327
12.44.4.5 m_disable_reported	327
12.44.4.6 m_pos	328
12.44.4.7 m_name	328

IX

12.44.4.8 m_data	28
12.44.4.9 m_char_list	28
12.44.4.10m_new_format	28
12.44.4.11m_global_bgsequence	:28
12.44.4.12m_ppqn	:28
12.44.4.13m_use_default_ppqn	28
12.44.4.14m_smf0_splitter	:28
12.45seq64::mutex Class Reference	329
12.45.1 Constructor & Destructor Documentation	30
12.45.1.1 mutex()	30
12.45.2 Member Function Documentation	30
12.45.2.1 lock() const	30
12.45.2.2 unlock() const	30
12.45.3 Field Documentation	30
12.45.3.1 sm_recursive_mutex	30
12.45.3.2 m_mutex_lock	30
12.46seq64::editable_event::name_value_t Struct Reference	30
12.46.1 Field Documentation	30
12.46.1.1 event_value	30
12.46.1.2 event_name	30
12.47seq64::options Class Reference	30
12.47.1 Member Enumeration Documentation	32
12.47.1.1 button	32
12.47.2 Constructor & Destructor Documentation	32
12.47.2.1 options(Gtk::Window &parent, perform &p)	32
12.47.3 Member Function Documentation	32
12.47.3.1 perf()	32
12.47.3.2 clock_callback_off(int bus, Gtk::RadioButton *button)	32
12.47.3.3 clock_callback_on(int bus, Gtk::RadioButton *button)	32
12.47.3.4 clock_callback_mod(int bus, Gtk::RadioButton *button)	32

12.47.3.5 clock_mod_callback(Gtk::Adjustment *adj)	32
12.47.3.6 input_callback(int bus, Gtk::Button *button)	32
12.47.3.7 filter_callback(Gtk::Button *button)	32
12.47.3.8 transport_callback(button type, Gtk::Button *button)	32
12.47.3.9 mouse_seq24_callback(Gtk::RadioButton *)	33
12.47.3.10mouse_fruity_callback(Gtk::RadioButton *)	33
12.47.3.11mouse_mod4_callback(Gtk::CheckButton *)	33
12.47.3.12mouse_snap_split_callback(Gtk::CheckButton *)	33
12.47.3.13ash_support_callback(Gtk::CheckButton *)	33
12.47.3.14add_midi_clock_page()	33
12.47.3.15add_midi_input_page()	33
12.47.3.16add_keyboard_page()	33
12.47.3.17add_mouse_page()	33
12.47.3.18add_jack_sync_page()	33
12.47.4 Field Documentation	33
12.47.4.1 m_tooltips	33
12.47.4.2 m_mainperf	33
12.47.4.3 m_button_ok	33
12.47.4.4 m_button_jack_transport	33
12.47.4.5 m_button_jack_master	33
12.47.4.6 m_button_jack_master_cond	33
12.47.4.7 m_button_jack_connect	33
12.47.4.8 m_button_jack_disconnect	33
12.47.4.9 m_notebook	33
12.48seq64::optionsfile Class Reference	34
12.48.1 Detailed Description	35
12.48.2 Constructor & Destructor Documentation	35
12.48.2.1 optionsfile(const std::string &name)	35
12.48.2.2 ~optionsfile()	35
12.48.3 Member Function Documentation	35

lxii CONTENTS

12.48.3.1 parse(perform &perf)	335
12.48.3.2 write(const perform &perf)	336
12.48.3.3 error_message(const std::string §ionname)	337
12.49seq64::perfedit Class Reference	337
12.49.1 Detailed Description	341
12.49.2 Constructor & Destructor Documentation	342
12.49.2.1 perfedit(perform &p, bool second_perfedit=false, int ppqn=SEQ64_USE_DEFA← ULT_PPQN)	342
12.49.2.2 ~perfedit()	342
12.49.3 Member Function Documentation	342
12.49.3.1 init_before_show()	342
12.49.3.2 enqueue_draw(bool forward=true)	342
12.49.3.3 zoom_check(int z)	342
12.49.3.4 enregister_peer(perfedit *peer)	343
12.49.3.5 set_zoom(int z)	343
12.49.3.6 set_beats_per_bar(int bpm)	343
12.49.3.7 set_beat_width(int bw)	343
12.49.3.8 set_snap(int snap)	343
12.49.3.9 set_guides()	343
12.49.3.10grow()	344
12.49.3.11set_looped()	344
12.49.3.12expand()	344
12.49.3.13collapse()	344
12.49.3.14copy()	344
12.49.3.15undo()	344
12.49.3.16redo()	344
12.49.3.17popup_menu(Gtk::Menu *menu)	344
12.49.3.18draw_sequences()	344
12.49.3.19(imeout()	344
12.49.3.20set_image(bool isrunning)	344
12.49.3.21start_playing()	345

12.49.3.22pause_playing()
12.49.3.23stop_playing()
12.49.3.24toggle_playing()
12.49.3.25on_realize()
12.49.3.26on_key_press_event(GdkEventKey *ev)
12.49.3.27on_delete_event(GdkEventAny *)
12.49.4 Friends And Related Function Documentation
12.49.4.1 update_perfedit_sequences
12.49.5 Field Documentation
12.49.5.1 m_peer_perfedit
12.49.5.2 m_table
12.49.5.3 m_vadjust
12.49.5.4 m_hadjust
12.49.5.5 m_vscroll
12.49.5.6 m_hscroll
12.49.5.7 m_perfnames
12.49.5.8 m_perfroll
12.49.5.9 m_perftime
12.49.5.10m_menu_snap
12.49.5.11m_image_play
12.49.5.12m_button_snap
12.49.5.13m_entry_snap
12.49.5.14m_button_stop
12.49.5.15m_button_play
12.49.5.16m_button_loop
12.49.5.17m_button_expand
12.49.5.18m_button_collapse
12.49.5.19m_button_copy
12.49.5.20m_button_grow
12.49.5.21m_button_undo

lxiv CONTENTS

12.49.5.22m_button_redo	. 347
12.49.5.23m_button_bpm	. 347
12.49.5.24m_entry_bpm	. 347
12.49.5.25m_button_bw	. 347
12.49.5.26m_entry_bw	. 347
12.49.5.27m_hbox	. 347
12.49.5.28m_hlbox	. 347
12.49.5.29m_tooltips	. 347
12.49.5.30m_menu_bpm	. 347
12.49.5.31m_menu_bw	. 347
12.49.5.32m_snap	. 347
12.49.5.33m_bpm	. 347
12.49.5.34m_bw	. 347
12.49.5.35m_ppqn	. 348
12.49.5.36m_is_running	. 348
12.49.5.37m_standard_bpm	. 348
12.49.5.37m_standard_bpm	
	. 348
12.50seq64::perfnames Class Reference	. 348 . 350
12.50seq64::perfnames Class Reference	. 348 . 350 . 350
12.50seq64::perfnames Class Reference	. 348 . 350 . 350
12.50seq64::perfnames Class Reference	. 348 . 350 . 350 . 350
12.50seq64::perfnames Class Reference	. 348 . 350 . 350 . 350 . 351
12.50seq64::perfnames Class Reference	. 348 . 350 . 350 . 350 . 351 . 351
12.50.seq64::perfnames Class Reference	. 348 . 350 . 350 . 350 . 351 . 351
12.50seq64::perfnames Class Reference	. 348 . 350 . 350 . 350 . 351 . 351 . 351
12.50seq64::perfnames Class Reference 12.50.1 Detailed Description 12.50.2 Constructor & Destructor Documentation 12.50.2.1 perfnames(perform &p, perfedit &parent, Gtk::Adjustment &vadjust) 12.50.2.2 ~perfnames() 12.50.3 Member Function Documentation 12.50.3.1 redraw_dirty_sequences() 12.50.3.2 enqueue_draw() 12.50.3.3 convert_y(int y)	. 348 . 350 . 350 . 351 . 351 . 351 . 351
12.50seq64::perfnames Class Reference 12.50.1 Detailed Description 12.50.2 Constructor & Destructor Documentation 12.50.2.1 perfnames(perform &p, perfedit &parent, Gtk::Adjustment &vadjust) 12.50.2.2 ~perfnames() 12.50.3 Member Function Documentation 12.50.3.1 redraw_dirty_sequences() 12.50.3.2 enqueue_draw() 12.50.3.3 convert_y(int y) 12.50.3.4 draw_sequences()	. 348 . 350 . 350 . 351 . 351 . 351 . 351
12.50seq64::perfnames Class Reference 12.50.1 Detailed Description 12.50.2 Constructor & Destructor Documentation 12.50.2.1 perfnames(perform &p, perfedit &parent, Gtk::Adjustment &vadjust) 12.50.2.2 ~perfnames() 12.50.3 Member Function Documentation 12.50.3.1 redraw_dirty_sequences() 12.50.3.2 enqueue_draw() 12.50.3.3 convert_y(int y) 12.50.3.4 draw_sequences() 12.50.3.5 draw_sequence(int sequence)	. 348 . 350 . 350 . 350 . 351 . 351 . 351 . 351
12.50seq64::perfnames Class Reference 12.50.1 Detailed Description 12.50.2 Constructor & Destructor Documentation 12.50.2.1 perfnames(perform &p, perfedit &parent, Gtk::Adjustment &vadjust) 12.50.2.2 ~perfnames() 12.50.3 Member Function Documentation 12.50.3.1 redraw_dirty_sequences() 12.50.3.2 enqueue_draw() 12.50.3.3 convert_y(int y) 12.50.3.4 draw_sequences() 12.50.3.5 draw_sequence(int sequence) 12.50.3.6 change_vert()	. 348 . 350 . 350 . 350 . 351 . 351 . 351 . 351 . 351

12.50.3.9 on_expose_event(GdkEventExpose *ev)	352
12.50.3.10on_button_press_event(GdkEventButton *ev)	352
12.50.3.11on_button_release_event(GdkEventButton *ev)	353
12.50.3.12on_size_allocate(Gtk::Allocation &)	354
12.50.3.13on_scroll_event(GdkEventScroll *ev)	354
12.50.4 Friends And Related Function Documentation	354
12.50.4.1 perfedit	354
12.50.5 Field Documentation	354
12.50.5.1 m_parent	354
12.50.5.2 m_names_chars	354
12.50.5.3 m_char_w	355
12.50.5.4 m_setbox_w	355
12.50.5.5 m_namebox_w	355
12.50.5.6 m_names_x	355
12.50.5.7 m_names_y	355
12.50.5.8 m_xy_offset	355
12.50.5.9 m_seqs_in_set	355
12.50.5.10m_sequence_max	355
12.50.5.11m_sequence_offset	355
12.50.5.12m_sequence_active	355
12.51seq64::perform Class Reference	355
12.51.1 Detailed Description	366
12.51.2 Member Enumeration Documentation	366
12.51.2.1 mute_op_t	366
12.51.2.2 ff_rw_button_t	367
12.51.3 Constructor & Destructor Documentation	367
12.51.3.1 perform(gui_assistant &mygui, int ppqn=SEQ64_USE_DEFAULT_PPQN)	367
12.51.3.2 ~perform()	367
12.51.4 Member Function Documentation	367
12.51.4.1 is_modified() const	367

lxvi CONTENTS

12.51.4.2 modify()
12.51.4.3 sequence_count() const
12.51.4.4 sequence_max() const
12.51.4.5 is_control_status() const
12.51.4.6 set_edit_sequence(int seqnum)
12.51.4.7 unset_edit_sequence(int seqnum)
12.51.4.8 is_edit_sequence(int seqnum) const
12.51.4.9 get_beats_per_bar() const
12.51.4.10set_beats_per_bar(int bpm)
12.51.4.11get_beat_width() const
12.51.4.12set_beat_width(int bw)
12.51.4.13clocks_per_metronome(int cpm)
12.51.4.14clocks_per_metronome() const
12.51.4.15set_32nds_per_quarter(int tpq)
12.51.4.16get_32nds_per_quarter() const
12.51.4.17us_per_quarter_note(long upqn)
12.51.4.1&us_per_quarter_note() const
12.51.4.19gui() const
12.51.4.20gui()
12.51.4.21keys() const
12.51.4.22keys()
12.51.4.23master_bus()
12.51.4.24 filter_by_channel(bool flag)
12.51.4.25s_running() const
12.51.4.26s_pattern_playing() const
12.51.4.27toggle_song_start_mode()
12.51.4.28song_start_mode(bool flag)
12.51.4.29song_start_mode() const
12.51.4.30s_jack_running() const
12.51.4.31is_jack_master() const

12.51.4.32s_paused() const
12.51.4.33s_pausable() const
12.51.4.34enregister(performcallback *pfcb)
12.51.4.35clear_all()
12.51.4.36aunch(int ppqn)
12.51.4.37new_sequence(int seq)
12.51.4.3&add_sequence(sequence *seq, int perf)
12.51.4.39delete_sequence(int seq)
12.51.4.40s_sequence_in_edit(int seq)
12.51.4.41clear_sequence_triggers(int seq)
12.51.4.42print_triggers() const
12.51.4.43finish()
12.51.4.44get_tick() const
12.51.4.45get_jack_tick() const
12.51.4.46set_jack_tick(midipulse tick)
12.51.4.47set_left_tick(midipulse tick, bool setstart=true)
12.51.4.4&get_left_tick() const
12.51.4.49set_start_tick(midipulse tick)
12.51.4.50get_start_tick() const
12.51.4.51set_right_tick(midipulse tick, bool setstart=true)
12.51.4.52get_right_tick() const
12.51.4.53eft_right_size() const
12.51.4.54move_triggers(bool direction)
12.51.4.55copy_triggers()
12.51.4.5@push_trigger_undo(int track=SEQ64_ALL_TRACKS)
12.51.4.57pop_trigger_undo()
12.51.4.5&pop_trigger_redo()
12.51.4.59have_undo() const
12.51.4.60set_have_undo(bool undo)
12.51.4.61have_redo() const

Ixviii CONTENTS

12.51.4.62set_have_redo(bool redo)
12.51.4.63split_trigger(int seqnum, midipulse tick)
12.51.4.64get_max_trigger()
12.51.4.65collapse()
12.51.4.66copy()
12.51.4.67expand()
12.51.4.68midi_control_toggle(int seq)
12.51.4.69midi_control_on(int seq)
12.51.4.70midi_control_off(int seq)
12.51.4.71handle_midi_control(int control, bool state)
12.51.4.72get_screen_set_notepad(int screen_set) const
12.51.4.73current_screen_set_notepad() const
12.51.4.74set_screen_set_notepad(int screenset, const std::string ¬e)
12.51.4.75set_screen_set_notepad(const std::string ¬e)
12.51.4.76get_screenset() const
12.51.4.77set_playing_screenset()
12.51.4.78set_screenset(int ss)
12.51.4.79get_playing_screenset() const
12.51.4.80any_group_unmutes() const
12.51.4.81mute_group_tracks()
12.51.4.82select_and_mute_group(int g_group)
12.51.4.83set_song_mute(mute_op_t op)
12.51.4.84set_mode_group_mute()
12.51.4.85unset_mode_group_mute()
12.51.4.86select_group_mute(int g_mute)
12.51.4.87set_mode_group_learn()
12.51.4.8&unset_mode_group_learn()
12.51.4.89s_group_learning()
12.51.4.90set_and_copy_mute_group(int group)
12.51.4.91start(bool state)

12.51.4.92stop()
12.51.4.93start_jack()
12.51.4.94stop_jack()
12.51.4.95position_jack(bool state)
12.51.4.96off_sequences()
12.51.4.97all_notes_off()
12.51.4.9&set_active(int seq, bool active)
12.51.4.99set_was_active(int seq)
12.51.4.106_dirty_main(int seq)
12.51.4.10s_dirty_edit(int seq)
12.51.4.108_dirty_perf(int seq)
12.51.4.103 _dirty_names(int seq)
12.51.4.10 6 _active(int seq) const
12.51.4.105jet_sequence(int seq) const
12.51.4.10@set_sequence(int seq)
12.51.4.10₹_exportable(int seq) const
12.51.4.10 Sest_sequences (bool pause=false)
12.51.4.10 Stay (midipulse tick)
12.51.4.11 st et_orig_ticks(midipulse tick)
12.51.4.11slet_beats_per_minute(int bpm)
12.51.4.11@et_beats_per_minute()
12.51.4.11 Set_looping (bool looping)
12.51.4.11stet_sequence_control_status(int status)
12.51.4.11@inset_sequence_control_status(int status)
12.51.4.11sequence_playing_toggle(int seq)
12.51.4.11sequence_playing_change(int seq, bool on)
12.51.4.11 Sequence_playing_on(int seq)
12.51.4.11sequence_playing_off(int seq)
12.51.4.12@ute_all_tracks(bool flag=true)
12.51.4.1 2t 0ggle_all_tracks()

IXX CONTENTS

12.51.4.122bute_screenset(int ss, bool flag=true)
12.51.4.123utput_func()
12.51.4.12Aput_func()
12.51.4.125et_group_mute_state(int gtrack, bool muted)
12.51.4.12@et_group_mute_state(int gtrack)
12.51.4.125et_offset(int offset)
12.51.4.12@et_offset() const
12.51.4.129ave_playing_state()
12.51.4.13@estore_playing_state()
12.51.4.13 dey_name(unsigned int k) const
12.51.4.13@get_key_events()
12.51.4.13@jet_key_groups()
12.51.4.13glet_key_events_rev()
12.51.4.135jet_key_groups_rev()
12.51.4.13show_ui_sequence_key() const
12.51.4.135/now_ui_sequence_key(bool flag)
12.51.4.138how_ui_sequence_number() const
12.51.4.139how_ui_sequence_number(bool flag)
12.51.4.1 40 okup_keyevent_key(int seqnum)
12.51.4.14thokup_keyevent_seq(unsigned int keycode)
12.51.4.1420okup_keygroup_key(long groupnum)
12.51.4.148okup_keygroup_group(unsigned int keycode)
12.51.4.14start_playing(bool songmode=false)
12.51.4.145ause_playing()
12.51.4.14⊤_playing()
12.51.4.14start_key(bool songmode=false)
12.51.4.14@ause_key(bool songmode=false)
12.51.4.14@top_key()
12.51.4.150earn_toggle()
12.51.4.15decrement_beats_per_minute()

12.51.4.15\(\textit{a}\)crement_beats_per_minute()
12.51.4.15@ecrement_screenset()
12.51.4.154crement_screenset()
12.51.4.155 ghlight(const sequence &seq) const
12.51.4.156_smf_0(const sequence &seq) const
12.51.4.15sequence_key(int seq)
12.51.4.15&equence_label(const sequence &seq)
12.51.4.15%et_input_bus(int bus, bool input_active)
12.51.4.16@nainwnd_key_event(const keystroke &k)
12.51.4.16plerfroll_key_event(const keystroke &k, int drop_sequence)
12.51.4.1621ayback_key_event(const keystroke &k, bool songmode=false)
12.51.4.1600ax_active_set() const
12.51.4.164unch_input_thread()
12.51.4.16aunch_output_thread()
12.51.4.1616it_jack()
12.51.4.16deinit_jack()
12.51.4.16&eq_in_playing_screen(int seq)
12.51.4.169_modified(bool flag)
12.51.4.176_midi_control_valid(int seq) const
12.51.4.17i\$_screenset_valid(int screenset) const
12.51.4.17\(\text{\text}_running(bool running) \\ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \
12.51.4.178_pattern_playing(bool flag)
12.51.4.17stet_playback_mode(bool playbackmode)
12.51.4.17faute_group_offset(int track)
12.51.4.176_seq_valid(int seq) const
12.51.4.1নাষ্ট_mseq_valid(int seq) const
12.51.4.17/8stall_sequence(sequence *seq, int seqnum)
12.51.4.171@ner_start(bool state)
12.51.4.180ner_stop(bool midiclock=false)
12.51.4.18dlamp_track(int track) const

Ixxii CONTENTS

12.51.4.182et_all_key_events()	397
12.51.4.18 Set_all_key_groups()	397
12.51.4.184et_key_event(unsigned int keycode, long sequence_slot)	397
12.51.4.18 Set_key_group(unsigned int keycode, long group_slot)	398
12.51.5 Friends And Related Function Documentation	398
12.51.5.1 jack_assistant	398
12.51.5.2 keybindentry	398
12.51.5.3 midifile	398
12.51.5.4 optionsfile	398
12.51.5.5 options	398
12.51.5.6 jack_sync_callback	398
12.51.6 Field Documentation	399
12.51.6.1 sm_mc_dummy	399
12.51.6.2 m_song_start_mode	399
12.51.6.3 m_gui_support	399
12.51.6.4 m_mute_group	399
12.51.6.5 m_tracks_mute_state	399
12.51.6.6 m_mode_group	399
12.51.6.7 m_mode_group_learn	399
12.51.6.8 m_mute_group_selected	399
12.51.6.9 m_playing_screen	399
12.51.6.10m_playscreen_offset	100
12.51.6.11m_seqs	100
12.51.6.12m_seqs_active	100
12.51.6.13m_was_active_main	100
12.51.6.14m_was_active_edit	100
12.51.6.15m_was_active_perf	100
12.51.6.16m_was_active_names	100
12.51.6.17m_sequence_state	100
12.51.6.18m_master_bus	100

12.51.6.19m_out_thread
12.51.6.20m_in_thread
12.51.6.21m_out_thread_launched
12.51.6.22m_in_thread_launched
12.51.6.23m_running
12.51.6.24m_is_pattern_playing
12.51.6.25m_inputing
12.51.6.26m_outputing
12.51.6.27m_looping
12.51.6.28m_playback_mode
12.51.6.29m_ppqn
12.51.6.30m_beats_per_bar
12.51.6.31m_beat_width
12.51.6.32m_clocks_per_metronome
12.51.6.33m_32nds_per_quarter
12.51.6.34m_us_per_quarter_note
12.51.6.35m_one_measure
12.51.6.36m_left_tick
12.51.6.37m_right_tick
12.51.6.38m_starting_tick
12.51.6.39m_tick
12.51.6.40m_jack_tick
12.51.6.41m_usemidiclock
12.51.6.42m_midiclockrunning
12.51.6.43m_midiclocktick
12.51.6.44m_midiclockpos
12.51.6.45m_is_paused
12.51.6.46m_screen_set_notepad
12.51.6.47m_midi_cc_toggle
12.51.6.48m_midi_cc_on

Ixxiv

12.51.6.49m_midi_cc_off	403
12.51.6.50m_offset	403
12.51.6.51m_control_status	403
12.51.6.52m_screenset	403
12.51.6.53m_seqs_in_set	403
12.51.6.54m_max_sets	403
12.51.6.55m_sequence_count	404
12.51.6.5@m_sequence_max	404
12.51.6.57m_edit_sequence	404
12.51.6.58m_is_modified	404
12.51.6.59m_condition_var	404
12.51.6.60m_jack_asst	404
12.51.6.61m_have_undo	404
12.51.6.62m_undo_vect	404
12.51.6.63m_have_redo	404
12.51.6.64m_redo_vect	404
12.51.6.65m_notify	404
12.52seq64::performcallback Struct Reference	404
12.52.1 Detailed Description	405
12.52.2 Member Function Documentation	406
12.52.2.1 on_grouplearnchange(bool)	406
12.53seq64::perfroll Class Reference	406
12.53.1 Constructor & Destructor Documentation	411
12.53.1.1 perfroll(perform &perf, perfedit &parent, Gtk::Adjustment &hadjust, Gtk::↔ Adjustment &vadjust, int ppqn=SEQ64_USE_DEFAULT_PPQN)	411
12.53.1.2 ~perfroll()	411
12.53.2 Member Function Documentation	411
12.53.2.1 set_guides(int snap, int measure, int beat)	411
12.53.2.2 update_sizes()	411
12.53.2.3 init_before_show()	411
12.53.2.4 fill_background_pixmap()	412

12.53.2.5 increment_size()
12.53.2.6 draw_all()
12.53.2.7 follow_progress()
12.53.2.8 redraw_progress()
12.53.2.9 draw_progress()
12.53.2.10redraw_dirty_sequences()
12.53.2.11set_ppqn(int ppqn)
12.53.2.12convert_xy(int x, int y, midipulse &ticks, int &seq)
12.53.2.13convert_x(int x, midipulse &ticks)
12.53.2.14snap_x(int &x)
12.53.2.15draw_sequence_on(int seqnum)
12.53.2.16draw_background_on(int seqnum)
12.53.2.17draw_drawable_row(long y)
12.53.2.1&hange_horz()
12.53.2.19change_vert()
12.53.2.20split_trigger(int sequence, midipulse tick)
12.53.2.21enqueue_draw()
12.53.2.2\(\text{\text{set_zoom(int z)}}\)
12.53.2.23horizontal_adjust(double step)
12.53.2.24vertical_adjust(double step)
12.53.2.25horizontal_set(double value)
12.53.2.26/vertical_set(double value)
12.53.2.27on_realize()
12.53.2.2&on_expose_event(GdkEventExpose *ev)
12.53.2.29on_button_press_event(GdkEventButton *ev)
12.53.2.30on_button_release_event(GdkEventButton *ev)
12.53.2.31on_motion_notify_event(GdkEventMotion *ev)
12.53.2.32on_scroll_event(GdkEventScroll *ev)
12.53.2.33on_focus_in_event(GdkEventFocus *ev)
12.53.2.34on_focus_out_event(GdkEventFocus *ev)

lxxvi CONTENTS

12.53.2.35on_size_allocate(Gtk::Allocation &al)
12.53.2.36on_key_press_event(GdkEventKey *ev)
12.53.2.37on_size_request(GtkRequisition *)
12.53.3 Friends And Related Function Documentation
12.53.3.1 FruityPerfInput
12.53.3.2 Seq24PerfInput
12.53.3.3 perfedit
12.53.4 Field Documentation
12.53.4.1 m_parent
12.53.4.2 m_h_page_increment
12.53.4.3 m_v_page_increment
12.53.4.4 m_snap
12.53.4.5 m_ppqn
12.53.4.6 m_page_factor
12.53.4.7 m_divs_per_beat
12.53.4.8 m_ticks_per_bar
12.53.4.9 m_perf_scale_x
12.53.4.10m_zoom
12.53.4.11m_names_y
12.53.4.12m_background_x
12.53.4.13m_size_box_w
12.53.4.14m_measure_length
12.53.4.15m_beat_length
12.53.4.16m_old_progress_ticks
12.53.4.17m_have_button_press
12.53.4.18m_4bar_offset
12.53.4.19m_sequence_offset
12.53.4.20m_roll_length_ticks
12.53.4.21m_drop_tick
12.53.4.22m_drop_tick_trigger_offset

12.53.4.23m_drop_sequence	419
12.53.4.24m_sequence_max	419
12.53.4.25m_sequence_active	419
12.53.4.26m_fruity_interaction	419
12.53.4.27m_seq24_interaction	419
12.53.4.28m_moving	419
12.53.4.29m_growing	419
12.53.4.30m_grow_direction	419
12.54seq64::perftime Class Reference	420
12.54.1 Constructor & Destructor Documentation	422
12.54.1.1 perftime(perform &perf, perfedit &parent, Gtk::Adjustment &hadjust, int ppqn=S↔ EQ64_USE_DEFAULT_PPQN)	422
12.54.1.2 ~perftime()	423
12.54.2 Member Function Documentation	423
12.54.2.1 reset()	423
12.54.2.2 set_scale(int scale)	423
12.54.2.3 set_guides(int snap, int measure)	423
12.54.2.4 increment_size()	423
12.54.2.5 enqueue_draw()	423
12.54.2.6 set_zoom(int z)	423
12.54.2.7 draw_background()	423
12.54.2.8 draw_progress_on_window()	423
12.54.2.9 change_horz()	424
12.54.2.10set_ppqn(int ppqn)	424
12.54.2.11tick_to_pixel(midipulse tick)	424
12.54.2.12pixel_to_tick(long pixel)	424
12.54.2.13tick_offset()	424
12.54.2.14update_sizes()	425
12.54.2.15dle_progress()	425
12.54.2.1@pdate_pixmap()	425
12.54.2.17draw_pixmap_on_window()	425

Ixxviii CONTENTS

12.54.2.18on_realize()	425
12.54.2.19on_expose_event(GdkEventExpose *ev)	425
12.54.2.20on_button_press_event(GdkEventButton *ev)	425
12.54.2.21on_size_allocate(Gtk::Allocation &r)	426
12.54.2.22on_button_release_event(GdkEventButton *)	426
12.54.2.23key_press_event(GdkEventKey *ev)	426
12.54.3 Friends And Related Function Documentation	426
12.54.3.1 perfedit	426
12.54.4 Field Documentation	426
12.54.4.1 m_parent	426
12.54.4.2 m_4bar_offset	426
12.54.4.3 m_tick_offset	427
12.54.4.4 m_ppqn	427
12.54.4.5 m_snap	427
12.54.4.6 m_measure_length	427
12.54.4.7 m_left_marker_tick	427
12.54.4.8 m_right_marker_tick	427
12.54.4.9 m_perf_scale_x	427
12.54.4.10m_timearea_y	427
12.55seq64::rc_settings Class Reference	427
12.55.1 Detailed Description	431
12.55.2 Constructor & Destructor Documentation	432
12.55.2.1 rc_settings()	432
12.55.2.2 rc_settings(const rc_settings &rhs)	432
12.55.3 Member Function Documentation	432
12.55.3.1 operator=(const rc_settings &rhs)	432
12.55.3.2 config_filespec() const	432
12.55.3.3 user_filespec() const	432
12.55.3.4 set_defaults()	432
12.55.3.5 auto_option_save() const	432

12.55.3.6 legacy_format() const
12.55.3.7 lash_support() const
12.55.3.8 allow_mod4_mode() const
12.55.3.9 allow_snap_split() const
12.55.3.10show_midi() const
12.55.3.11priority() const
12.55.3.12stats() const
12.55.3.13pass_sysex() const
12.55.3.14with_jack_transport() const
12.55.3.15with_jack_master() const
12.55.3.16with_jack_master_cond() const
12.55.3.17with_jack() const
12.55.3.18song_start_mode() const
12.55.3.19filter_by_channel() const
12.55.3.20manual_alsa_ports() const
12.55.3.21reveal_alsa_ports() const
12.55.3.22print_keys() const
12.55.3.23device_ignore() const
12.55.3.24device_ignore_num() const
12.55.3.25nteraction_method() const
12.55.3.26 ilename() const
12.55.3.27jack_session_uuid() const
12.55.3.28ast_used_dir() const
12.55.3.29config_directory() const
12.55.3.3@config_filename() const
12.55.3.31user_filename() const
12.55.3.32config_filename_alt() const
12.55.3.33user_filename_alt() const
12.55.3.34auto_option_save(bool flag)
12.55.3.35egacy_format(bool flag)

IXXX

12.55.3.	36ash_support(bool flag)	434
12.55.3.	37allow_mod4_mode(bool flag)	434
12.55.3.	38allow_snap_split(bool flag)	434
12.55.3.	39show_midi(bool flag)	434
12.55.3.	40priority(bool flag)	434
12.55.3.	41stats(bool flag)	434
12.55.3.	42pass_sysex(bool flag)	434
12.55.3.	43with_jack_transport(bool flag)	434
12.55.3.	44with_jack_master(bool flag)	434
12.55.3.	45with_jack_master_cond(bool flag)	434
12.55.3.	46song_start_mode(bool flag)	434
12.55.3.	47filter_by_channel(bool flag)	434
12.55.3.	48manual_alsa_ports(bool flag)	434
12.55.3.	49reveal_alsa_ports(bool flag)	434
12.55.3.	50print_keys(bool flag)	434
12.55.3.	51device_ignore(bool flag)	434
12.55.3.	52device_ignore_num(int value)	434
12.55.3.	53nteraction_method(interaction_method_t value)	435
12.55.3.	54filename(const std::string &value)	435
12.55.3.	55jack_session_uuid(const std::string &value)	435
12.55.3.	56dast_used_dir(const std::string &value)	435
12.55.3.	57config_directory(const std::string &value)	435
12.55.3.	5&set_config_files(const std::string &value)	435
12.55.3.	59config_filename(const std::string &value)	435
12.55.3.	60user_filename(const std::string &value)	436
12.55.3.	61config_filename_alt(const std::string &value)	436
12.55.3.	62user_filename_alt(const std::string &value)	436
12.55.3.0	63nome_config_directory() const	436
12.55.4 Friends A	And Related Function Documentation	436
12.55.4.	1 optionsfile	436

	12.55.4.2 options	436
	12.55.4.3 mainwnd	436
	12.55.4.4 parse_command_line_options	436
	12.55.4.5 help_check	437
12.55.5	5 Field Documentation	437
	12.55.5.1 m_auto_option_save	437
	12.55.5.2 m_legacy_format	437
	12.55.5.3 m_lash_support	437
	12.55.5.4 m_allow_mod4_mode	437
	12.55.5.5 m_allow_snap_split	437
	12.55.5.6 m_show_midi	437
	12.55.5.7 m_priority	437
	12.55.5.8 m_stats	437
	12.55.5.9 m_pass_sysex	437
	12.55.5.10m_with_jack_transport	437
	12.55.5.11m_with_jack_master	438
	12.55.5.12m_with_jack_master_cond	438
	12.55.5.13m_song_start_mode	438
	12.55.5.14m_filter_by_channel	438
	12.55.5.15m_manual_alsa_ports	438
	12.55.5.16m_reveal_alsa_ports	438
	12.55.5.17m_print_keys	438
	12.55.5.18m_device_ignore	438
	12.55.5.19m_device_ignore_num	438
	12.55.5.20m_interaction_method	438
	12.55.5.21m_filename	438
	12.55.5.22m_jack_session_uuid	438
	12.55.5.23m_last_used_dir	438
	12.55.5.24m_config_directory	438
	12.55.5.25m_config_filename	438

Ixxxii CONTENTS

12.55.5.26m_user_filename
12.55.5.27m_config_filename_alt
12.55.5.28m_user_filename_alt
12.56seq64::rect Class Reference
12.56.1 Field Documentation
12.56.1.1 x
12.56.1.2 y
12.56.1.3 height
12.56.1.4 width
12.57seq64::gui_drawingarea_gtk2::rect Struct Reference
12.57.1 Field Documentation
12.57.1.1 x
12.57.1.2 y
12.57.1.3 height
12.57.1.4 width
12.58seq64::Seq24PerfInput Class Reference
12.58.1 Constructor & Destructor Documentation
12.58.1.1 Seq24PerfInput()
12.58.2 Member Function Documentation
12.58.2.1 on_button_press_event(GdkEventButton *a_ev, perfroll &roll) 44
12.58.2.2 on_button_release_event(GdkEventButton *a_ev, perfroll &roll) 44
12.58.2.3 on_motion_notify_event(GdkEventMotion *a_ev, perfroll &roll)
12.58.2.4 set_adding(bool a_adding, perfroll &roll)
12.58.2.5 handle_motion_key(bool is_left, perfroll &roll)
12.58.2.6 is_adding() const
12.58.3 Friends And Related Function Documentation
12.58.3.1 perfroll
12.58.4 Field Documentation
12.58.4.1 m_adding
12.58.4.2 m_effective_tick

12.59seq64::Seq24SeqEventInput Struct Reference	442
12.59.1 Constructor & Destructor Documentation	443
12.59.1.1 Seq24SeqEventInput()	443
12.59.2 Member Function Documentation	443
12.59.2.1 set_adding(bool adding, seqevent &ths)	443
12.59.2.2 on_button_press_event(GdkEventButton *ev, seqevent &ths)	443
12.59.2.3 on_button_release_event(GdkEventButton *ev, seqevent &ths)	444
12.59.2.4 on_motion_notify_event(GdkEventMotion *ev, seqevent &ths)	444
12.59.3 Field Documentation	444
12.59.3.1 m_adding	444
12.60seq64::seqdata Class Reference	444
12.60.1 Constructor & Destructor Documentation	447
12.60.1.1 seqdata(sequence &seq, perform &p, int zoom, Gtk::Adjustment &hadjust)	447
12.60.1.2 ~seqdata()	448
12.60.2 Member Function Documentation	448
12.60.2.1 reset()	448
12.60.2.2 redraw()	448
12.60.2.3 set_zoom(int a_zoom)	448
12.60.2.4 set_data_type(midibyte status, midibyte control)	448
12.60.2.5 idle_redraw()	448
12.60.2.6 update_sizes()	448
12.60.2.7 update_pixmap()	449
12.60.2.8 draw_line_on_window()	449
12.60.2.9 xy_to_rect(int x1, int y1, int x2, int y2, int ℞, int &ry, int &rw, int &rh)	449
12.60.2.10draw_events_on(Glib::RefPtr< Gdk::Drawable > drawable)	449
12.60.2.11change_horz()	449
12.60.2.12convert_x(int x, midipulse &tick)	450
12.60.2.13render_number(Glib::RefPtr< Gdk::Pixmap > &pixmap, int x, int y, const char *const num)	450
12.60.2.14draw_events_on_pixmap()	450
12.60.2.15draw_pixmap_on_window()	450

IXXXIV

12.60.2.1\&n_realize()	450
12.60.2.17on_expose_event(GdkEventExpose *ev)	450
12.60.2.18on_button_press_event(GdkEventButton *ev)	450
12.60.2.19on_button_release_event(GdkEventButton *ev)	451
12.60.2.20on_motion_notify_event(GdkEventMotion *ev)	451
12.60.2.21on_leave_notify_event(GdkEventCrossing *ev)	451
12.60.2.22on_scroll_event(GdkEventScroll *ev)	451
12.60.2.23on_size_allocate(Gtk::Allocation &)	452
12.60.3 Friends And Related Function Documentation	452
12.60.3.1 Ifownd	452
12.60.3.2 seqevent	452
12.60.3.3 seqroll	452
12.60.4 Field Documentation	452
12.60.4.1 m_seq	452
12.60.4.2 m_zoom	452
12.60.4.3 m_scroll_offset_ticks	452
12.60.4.4 m_scroll_offset_x	452
12.60.4.5 m_number_w	452
12.60.4.6 m_number_h	452
12.60.4.7 m_number_offset_y	452
12.60.4.8 m_status	453
12.60.4.9 m_cc	453
12.60.4.10m_numbers	453
12.60.4.11m_old	453
12.60.4.12m_dragging	453
12.61seq64::seqedit Class Reference	453
12.61.1 Detailed Description	460
12.61.2 Constructor & Destructor Documentation	460
12.61.2.1 seqedit(perform &perf, sequence &seq, int pos, int ppqn=SEQ64_USE_DEFA⇔ ULT_PPQN)	460
12.61.2.2 ~seqedit()	460

12.61.3	Member Function Documentation	460
	12.61.3.1 set_zoom(int zoom)	460
	12.61.3.2 set_snap(int snap)	461
	12.61.3.3 set_note_length(int note_length)	461
	12.61.3.4 set_beats_per_bar(int bpm)	461
	12.61.3.5 set_beat_width(int bw)	461
	12.61.3.6 set_rec_vol(int recvol)	461
	12.61.3.7 horizontal_adjust(double step)	462
	12.61.3.8 vertical_adjust(double step)	462
	12.61.3.9 horizontal_set(double value)	462
	12.61.3.10vertical_set(double value)	462
	12.61.3.11set_measures(int lim)	462
	12.61.3.12apply_length(int bpm, int bw, int measures)	462
	12.61.3.13get_measures()	463
	12.61.3.14set_midi_channel(int midichannel)	463
	12.61.3.15set_midi_bus(int midibus)	463
	12.61.3.16set_scale(int scale)	463
	12.61.3.17set_key(int note)	463
	12.61.3.18set_background_sequence(int seq)	463
	12.61.3.19name_change_callback()	463
	12.61.3.20play_change_callback()	464
	12.61.3.21record_change_callback()	464
	12.61.3.22q_rec_change_callback()	464
	12.61.3.23thru_change_callback()	464
	12.61.3.24undo_callback()	464
	12.61.3.25redo_callback()	464
	12.61.3.26set_data_type(midibyte status, midibyte control=0)	464
	12.61.3.27update_all_windows()	464
	12.61.3.28fill_top_bar()	464
	12.61.3.29create_menus()	465

IXXXVI

12.61.3.30popup_menu(Gtk::Menu *menu)	465
12.61.3.31popup_event_menu()	465
12.61.3.32popup_midibus_menu()	465
12.61.3.33popup_sequence_menu()	465
12.61.3.34popup_tool_menu()	465
12.61.3.35popup_midich_menu()	466
12.61.3.36create_menu_image(bool state=false)	466
12.61.3.37timeout()	466
12.61.3.3&do_action(int action, int var)	466
12.61.3.39mouse_action(mouse_action_e action)	466
12.61.3.40change_focus(bool set_it=true)	466
12.61.3.41handle_close()	466
12.61.3.42on_realize()	466
12.61.3.43on_set_focus(Widget *focus)	466
12.61.3.44on_focus_in_event(GdkEventFocus *)	466
12.61.3.45on_focus_out_event(GdkEventFocus *)	466
12.61.3.46on_delete_event(GdkEventAny *event)	466
12.61.3.47on_scroll_event(GdkEventScroll *ev)	467
12.61.3.4&n_key_press_event(GdkEventKey *ev)	467
12.61.4 Field Documentation	467
12.61.4.1 seqmenu	468
12.61.4.2 m_initial_snap	468
12.61.4.3 m_initial_note_length	468
12.61.4.4 m_initial_zoom	468
12.61.4.5 m_zoom	468
12.61.4.6 m_snap	468
12.61.4.7 m_note_length	468
12.61.4.8 m_scale	468
12.61.4.9 m_key	468
12.61.4.10m_bgsequence	468

12.61.4.11m_measures	8
12.61.4.12m_ppqn	8
12.61.4.13m_seq	8
12.61.4.14m_menubar	8
12.61.4.15m_menu_tools	9
12.61.4.16m_menu_zoom	9
12.61.4.17m_menu_snap	9
12.61.4.18m_menu_note_length	9
12.61.4.19m_menu_length	9
12.61.4.20m_menu_midich	9
12.61.4.21m_menu_midibus	9
12.61.4.22m_menu_data	9
12.61.4.23m_menu_key	9
12.61.4.24m_menu_scale	9
12.61.4.25m_menu_sequences	9
12.61.4.26m_menu_bpm	9
12.61.4.27m_menu_bw	9
12.61.4.28m_menu_rec_vol	9
12.61.4.29m_vadjust	9
12.61.4.30m_hadjust	9
12.61.4.31m_vscroll_new	9
12.61.4.32m_hscroll_new	9
12.61.4.33m_seqkeys_wid	9
12.61.4.34m_seqtime_wid	9
12.61.4.35m_seqdata_wid	0
12.61.4.36m_seqevent_wid	0
12.61.4.37m_seqroll_wid	0
12.61.4.38m_table	0
12.61.4.39m_vbox	0
12.61.4.40m_hbox	0

Ixxxviii CONTENTS

12.61.4.41m_hbox2
12.61.4.42m_button_undo
12.61.4.43m_button_redo
12.61.4.44m_button_quantize
12.61.4.45m_button_tools
12.61.4.46m_button_sequence
12.61.4.47m_entry_sequence
12.61.4.48m_button_bus
12.61.4.49m_entry_bus
12.61.4.50m_button_channel
12.61.4.51m_entry_channel
12.61.4.52m_button_snap
12.61.4.53m_entry_snap
12.61.4.54m_button_note_length
12.61.4.55m_entry_note_length
12.61.4.56m_button_zoom
12.61.4.57m_entry_zoom
12.61.4.58m_button_length
12.61.4.59m_entry_length
12.61.4.60m_button_key
12.61.4.61m_entry_key
12.61.4.62m_button_scale
12.61.4.63m_entry_scale
12.61.4.64m_tooltips
12.61.4.65m_button_data
12.61.4.66m_entry_data
12.61.4.67m_button_bpm
12.61.4.68m_entry_bpm
12.61.4.69m_button_bw
12.61.4.70m_entry_bw

12.61.4.71m_button_rec_vol	471
12.61.4.72m_toggle_play	471
12.61.4.73m_toggle_record	471
12.61.4.74m_toggle_q_rec	471
12.61.4.75m_toggle_thru	471
12.61.4.76m_entry_name	471
12.61.4.77m_editing_status	471
12.61.4.78m_editing_cc	472
12.61.4.79m_have_focus	472
12.62seq64::seqevent Class Reference	472
12.62.1 Constructor & Destructor Documentation	475
12.62.1.1 seqevent(perform &p, sequence &seq, int zoom, int snap, seqdata &seqdata_wid, Gtk::Adjustment &hadjust, int ppqn=SEQ64_USE_DEFAULT_PPQN)	
12.62.1.2 ~seqevent()	475
12.62.2 Member Function Documentation	475
12.62.2.1 reset()	475
12.62.2.2 redraw()	476
12.62.2.3 set_zoom(int zoom)	476
12.62.2.4 set_snap(int snap)	476
12.62.2.5 set_data_type(midibyte status, midibyte control)	476
12.62.2.6 update_sizes()	476
12.62.2.7 draw_background()	476
12.62.2.8 draw_events_on_pixmap()	476
12.62.2.9 draw_pixmap_on_window()	476
12.62.2.1@raw_selection_on_window()	477
12.62.2.11update_pixmap()	477
12.62.2.12force_draw()	477
12.62.2.13dle_redraw()	477
12.62.2.14x_to_w(int x1, int x2, int &x, int &w)	477
12.62.2.15drop_event(midipulse tick)	477
12.62.2.16draw_events_on(Glib::RefPtr< Gdk::Drawable > draw)	477

xc CONTENTS

12.62.2.1 /start_paste()	8
12.62.2.1&hange_horz()	8
12.62.2.19convert_x(int x, midipulse &tick)	8
12.62.2.20convert_t(midipulse tick, int &x)	8
12.62.2.21snap_y(int &y)	8
12.62.2.2\section nap_x(int \&x)	8
12.62.2.23on_realize()	9
12.62.2.24on_expose_event(GdkEventExpose *ev)	9
12.62.2.25on_button_press_event(GdkEventButton *ev)	9
12.62.2.26on_button_release_event(GdkEventButton *ev)	9
12.62.2.27on_motion_notify_event(GdkEventMotion *ev)	0
12.62.2.28on_focus_in_event(GdkEventFocus *)	0
12.62.2.29on_focus_out_event(GdkEventFocus *)	0
12.62.2.30on_key_press_event(GdkEventKey *p0)	0
12.62.2.31on_size_allocate(Gtk::Allocation &)	1
12.62.3 Friends And Related Function Documentation	1
12.62.3.1 FruitySeqEventInput	1
12.62.3.2 Seq24SeqEventInput	1
12.62.4 Field Documentation	1
12.62.4.1 m_fruity_interaction	1
12.62.4.2 m_seq24_interaction	1
12.62.4.3 m_seq	1
12.62.4.4 m_zoom	1
12.62.4.5 m_snap	1
12.62.4.6 m_ppqn	1
12.62.4.7 m_old	1
12.62.4.8 m_selected	1
12.62.4.9 m_scroll_offset_ticks	1
12.62.4.10m_scroll_offset_x	1
12.62.4.11m_seqdata_wid	2

CONTENTS xci

12.62.4.12m_selecting	482
12.62.4.13m_moving_init	482
12.62.4.14m_moving	482
12.62.4.15m_growing	482
12.62.4.16m_painting	482
12.62.4.17m_paste	482
12.62.4.18m_move_snap_offset_x	482
12.62.4.19m_status	482
12.62.4.20m_cc	482
12.63seq64::seqkeys Class Reference	482
12.63.1 Detailed Description	485
12.63.2 Constructor & Destructor Documentation	485
12.63.2.1 seqkeys(sequence &seq, perform &p, Gtk::Adjustment &vadjust)	485
12.63.2.2 ~seqkeys()	485
12.63.3 Member Function Documentation	486
12.63.3.1 set_scale(int scale)	486
12.63.3.2 set_key(int key)	486
12.63.3.3 set_hint_key(int key)	486
12.63.3.4 set_hint_state(bool state)	486
12.63.3.5 force_draw()	486
12.63.3.6 set_listen_button_press(GdkEventButton *ev)	486
12.63.3.7 set_listen_button_release(GdkEventButton *ev)	487
12.63.3.8 set_listen_motion_notify(GdkEventMotion *ev)	487
12.63.3.9 draw_area()	487
12.63.3.10update_pixmap()	487
12.63.3.11convert_y(int y, int ¬e)	487
12.63.3.12draw_key(int key, bool state)	487
12.63.3.13change_vert()	487
12.63.3.14update_sizes()	487
12.63.3.15reset()	487

xcii CONTENTS

12.63.3.16s_black_key(int key) const	487
12.63.3.17on_realize()	488
12.63.3.18on_expose_event(GdkEventExpose *ev)	488
12.63.3.19on_button_press_event(GdkEventButton *ev)	488
12.63.3.20on_button_release_event(GdkEventButton *ev)	488
12.63.3.21on_motion_notify_event(GdkEventMotion *p0)	489
12.63.3.22on_enter_notify_event(GdkEventCrossing *p0)	489
12.63.3.23on_leave_notify_event(GdkEventCrossing *p0)	489
12.63.3.24on_scroll_event(GdkEventScroll *ev)	489
12.63.3.25on_size_allocate(Gtk::Allocation &)	489
12.63.4 Friends And Related Function Documentation	490
12.63.4.1 seqroll	490
12.63.4.2 FruitySeqRollInput	490
12.63.5 Field Documentation	490
12.63.5.1 m_seq	490
12.63.5.2 m_scroll_offset_key	490
12.63.5.3 m_scroll_offset_y	490
12.63.5.4 m_hint_state	490
12.63.5.5 m_hint_key	490
12.63.5.6 m_keying	490
12.63.5.7 m_keying_note	490
12.63.5.8 m_scale	490
12.63.5.9 m_key	490
12.63.5.10m_show_octave_letters	490
12.64seq64::seqmenu Class Reference	491
12.64.1 Detailed Description	493
12.64.2 Constructor & Destructor Documentation	493
12.64.2.1 seqmenu(perform &a_p)	493
12.64.2.2 ~seqmenu()	494
12.64.3 Member Function Documentation	494

CONTENTS xciii

12.64.3.1 current_seq() const
12.64.3.2 is_modified() const
12.64.3.3 current_seq(int seq)
12.64.3.4 set_edit_sequence(int seqnum)
12.64.3.5 unset_edit_sequence(int seqnum)
12.64.3.6 is_edit_sequence(int seqnum) const
12.64.3.7 is_modified(bool flag)
12.64.3.8 get_current_sequence() const
12.64.3.9 get_sequence(int seqnum) const
12.64.3.10s_current_seq_active() const
12.64.3.11is_current_seq_in_edit() const
12.64.3.12new_current_sequence()
12.64.3.13new_sequence(int seqnum)
12.64.3.14delete_current_sequence()
12.64.3.15toggle_current_sequence()
12.64.3.16popup_menu()
12.64.3.17seq_edit()
12.64.3.18seq_event_edit()
12.64.3.19seq_set_and_edit(int seqnum)
12.64.3.20seq_set_and_eventedit(int seqnum)
12.64.3.21seq_new()
12.64.3.22seq_copy()
12.64.3.23seq_cut()
12.64.3.24seq_paste()
12.64.3.25seq_clear_perf()
12.64.3.26set_bus_and_midi_channel(int a_bus, int a_ch)
12.64.3.27set_transposable(bool flag)
12.64.3.28mute_all_tracks()
12.64.3.29unmute_all_tracks()
12.64.3.30toggle_all_tracks()

xciv CONTENTS

12.64.3.31redraw(int a_sequence)=0	497
12.64.3.32on_realize()	497
12.64.4 Field Documentation	497
12.64.4.1 m_menu	497
12.64.4.2 m_mainperf	497
12.64.4.3 m_clipboard	497
12.64.4.4 m_seqedit	497
12.64.4.5 m_eventedit	497
12.64.4.6 m_current_seq	497
12.64.4.7 m_modified	497
12.65seq64::seqroll Class Reference	497
12.65.1 Constructor & Destructor Documentation	503
12.65.1.1 seqroll(perform &perf, sequence &seq, int zoom, int snap, seqkeys &seqkeys_wid, int pos, Gtk::Adjustment &hadjust, Gtk::Adjustment &vadjust, int ppqn=SEQ64←	
USE_DEFAULT_PPQN)	503
12.65.1.2 ~seqroll()	504
12.65.2 Member Function Documentation	504
12.65.2.1 set_snap(int snap)	504
12.65.2.2 set_zoom(int zoom)	504
12.65.2.3 set_note_length(int note_length)	504
12.65.2.4 note_off_length() const	504
12.65.2.5 add_note(midipulse tick, int note, bool paint=true)	504
12.65.2.6 set_key(int key)	504
12.65.2.7 set_scale(int scale)	505
12.65.2.8 set_data_type(midibyte status, midibyte control)	505
12.65.2.9 set_background_sequence(bool state, int seq)	505
12.65.2.10update_pixmap()	505
12.65.2.11update_sizes()	505
12.65.2.12update_background()	505
12.65.2.13draw_background_on_pixmap()	505
12.65.2.14draw_events_on_pixmap()	505

CONTENTS xcv

12.65.2.15draw_selection_on_window())6
12.65.2.16draw_progress_on_window())6
12.65.2.17reset())6
12.65.2.1&update_and_draw(int force=false))6
12.65.2.19redraw())6
12.65.2.20redraw_events())6
12.65.2.21start_paste())7
12.65.2.22complete_paste())7
12.65.2.23complete_paste(int x, int y))7
12.65.2.24follow_progress())7
12.65.2.25force_draw())7
12.65.2.26horizontal_adjust(double step))7
12.65.2.27vertical_adjust(double step))7
12.65.2.28snap_y(int &y))7
12.65.2.29snap_x(int &x))7
12.65.2.30convert_xy(int x, int y, midipulse &ticks, int ¬e))8
12.65.2.31convert_tn(midipulse ticks, int note, int &x, int &y))8
12.65.2.32xy_to_rect(int x1, int y1, int x2, int y2, int &x, int &y, int &w, int &h) 50)8
12.65.2.3convert_tn_box_to_rect(midipulse tick_s, midipulse tick_f, int note_h, int note_l, int &x, int &y, int &w, int &h))8
12.65.2.34convert_sel_box_to_rect(midipulse tick_s, midipulse tick_f, int note_h, int note_l) 50)9
12.65.2.35get_selected_box(midipulse &tick_s, int ¬e_h, midipulse &tick_f, int ¬e_l) . 50)9
12.65.2.36draw_events_on(Glib::RefPtr< Gdk::Drawable > draw))9
12.65.2.37dle_redraw())9
12.65.2.38dle_progress())9
12.65.2.39change_horz())9
12.65.2.40change_vert()	0
12.65.2.41move_selection_box(int dx, int dy)	0
12.65.2.42move_selected_notes(int dx, int dy)	0
12.65.2.43grow_selected_notes(int dx)	0
12.65.2.44set adding(bool adding)	11

xcvi CONTENTS

12.65.2.45update_mouse_pointer(bool adding=false)	511
12.65.2.46button_press_initial(GdkEventButton *ev, int &norm_x, int &snapped_x, int &snapped_y)	511
12.65.2.47align_selection(midipulse &tick_s, int ¬e_h, midipulse &tick_f, int ¬e_l, int snapped_x)	511
12.65.2.48button_press(GdkEventButton *ev)	511
12.65.2.49button_release(GdkEventButton *ev)	511
12.65.2.50motion_notify(GdkEventMotion *ev)	512
12.65.2.51clear_selected()	512
12.65.2.52clear_old()	512
12.65.2.53clear_flags()	512
12.65.2.54scroll_offset_x(int x) const	512
12.65.2.55scroll_offset_y(int y) const	512
12.65.2.56set_current_offset_x_y(int x, int y)	513
12.65.2.57adding() const	513
12.65.2.5&electing() const	513
12.65.2.59growing() const	513
12.65.2.60normal_action() const	513
12.65.2.61select_action() const	513
12.65.2.62drop_action() const	514
12.65.2.63moving() const	514
12.65.2.64on_realize()	514
12.65.2.65on_expose_event(GdkEventExpose *ev)	514
12.65.2.66on_button_press_event(GdkEventButton *ev)	514
12.65.2.67on_button_release_event(GdkEventButton *ev)	514
12.65.2.6&n_motion_notify_event(GdkEventMotion *ev)	515
12.65.2.69on_focus_in_event(GdkEventFocus *)	515
12.65.2.70on_focus_out_event(GdkEventFocus *)	515
12.65.2.71on_key_press_event(GdkEventKey *ev)	515
12.65.2.72on_scroll_event(GdkEventScroll *a_ev)	516
12.65.2.73on_size_allocate(Gtk::Allocation &)	516

CONTENTS xcvii

12.65.2.74on_leave_notify_event(GdkEventCrossing *p0)
12.65.2.75on_enter_notify_event(GdkEventCrossing *p0)
12.65.3 Friends And Related Function Documentation
12.65.3.1 FruitySeqRollInput
12.65.3.2 seqedit
12.65.4 Field Documentation
12.65.4.1 m_horizontal_adjust
12.65.4.2 m_vertical_adjust
12.65.4.3 m_old
12.65.4.4 m_selected
12.65.4.5 m_seq
12.65.4.6 m_seqkeys_wid
12.65.4.7 m_fruity_interaction
12.65.4.8 m_pos
12.65.4.9 m_zoom
12.65.4.10m_snap
12.65.4.11m_ppqn
12.65.4.12m_note_length
12.65.4.13m_scale
12.65.4.14m_key
12.65.4.15m_adding
12.65.4.16m_selecting
12.65.4.17m_moving
12.65.4.18m_moving_init
12.65.4.19m_growing
12.65.4.20m_painting
12.65.4.21m_paste
12.65.4.22m_is_drag_pasting
12.65.4.23m_is_drag_pasting_start
12.65.4.24m_justselected_one

xcviii CONTENTS

	519
12.65.4.26m_move_delta_y	519
12.65.4.27m_move_snap_offset_x	519
12.65.4.28m_progress_x	519
12.65.4.29m_scroll_offset_ticks	519
12.65.4.30m_scroll_offset_key	519
12.65.4.31m_scroll_offset_x	519
12.65.4.32m_scroll_offset_y	519
12.65.4.33m_background_sequence	519
12.65.4.34m_drawing_background_seq	519
12.65.4.35m_status	519
12.65.4.36m_cc	519
12.66seq64::seqtime Class Reference	519
12.66.1 Constructor & Destructor Documentation	521
12.66.1.1 seqtime(sequence &seq, perform &p, int zoom, Gtk::Adjustment &hadjust, int ppqn=SEQ64_USE_DEFAULT_PPQN)	
12.66.1.2 ~seqtime()	522
12.66.2 Member Function Documentation	
12.66.2 Member Function Documentation	522
	522 522
12.66.2.1 reset()	522 522 522
12.66.2.1 reset()	522 522 522 522
12.66.2.1 reset()	522 522 522 522 522
12.66.2.1 reset() 12.66.2.2 redraw() 12.66.2.3 set_zoom(int zoom) 12.66.2.4 draw_pixmap_on_window()	522 522 522 522 522 522
12.66.2.1 reset() 12.66.2.2 redraw() 12.66.2.3 set_zoom(int zoom) 12.66.2.4 draw_pixmap_on_window() 12.66.2.5 draw_progress_on_window()	522 522 522 522 522 522 522
12.66.2.1 reset() 12.66.2.2 redraw() 12.66.2.3 set_zoom(int zoom) 12.66.2.4 draw_pixmap_on_window() 12.66.2.5 draw_progress_on_window() 12.66.2.6 update_pixmap()	522 522 522 522 522 522 522 522
12.66.2.1 reset() 12.66.2.2 redraw() 12.66.2.3 set_zoom(int zoom) 12.66.2.4 draw_pixmap_on_window() 12.66.2.5 draw_progress_on_window() 12.66.2.6 update_pixmap() 12.66.2.7 change_horz()	522 522 522 522 522 522 522 522 522
12.66.2.1 reset() 12.66.2.2 redraw() 12.66.2.3 set_zoom(int zoom) 12.66.2.4 draw_pixmap_on_window() 12.66.2.5 draw_progress_on_window() 12.66.2.6 update_pixmap() 12.66.2.7 change_horz() 12.66.2.8 update_sizes()	522 522 522 522 522 522 522 522 522
12.66.2.1 reset() 12.66.2.2 redraw() 12.66.2.3 set_zoom(int zoom) 12.66.2.4 draw_pixmap_on_window() 12.66.2.5 draw_progress_on_window() 12.66.2.6 update_pixmap() 12.66.2.7 change_horz() 12.66.2.8 update_sizes() 12.66.2.9 idle_progress()	522 522 522 522 522 522 522 522 522 522
12.66.2.1 reset() 12.66.2.2 redraw() 12.66.2.3 set_zoom(int zoom) 12.66.2.4 draw_pixmap_on_window() 12.66.2.5 draw_progress_on_window() 12.66.2.6 update_pixmap() 12.66.2.7 change_horz() 12.66.2.8 update_sizes() 12.66.2.9 idle_progress() 12.66.2.10on_realize()	522 522 522 522 522 522 522 522 522 522

CONTENTS xcix

12.66.2.14on_button_release_event(GdkEventButton *)	523
12.66.3 Field Documentation	523
12.66.3.1 m_seq	523
12.66.3.2 m_scroll_offset_ticks	523
12.66.3.3 m_scroll_offset_x	523
12.66.3.4 m_zoom	523
12.66.3.5 m_ppqn	523
12.67seq64::sequence Class Reference	523
12.67.1 Detailed Description	33
12.67.2 Member Typedef Documentation	33
12.67.2.1 EventStack	33
12.67.3 Member Enumeration Documentation	33
12.67.3.1 select_action_e	33
12.67.4 Constructor & Destructor Documentation	33
12.67.4.1 sequence(int ppqn=SEQ64_USE_DEFAULT_PPQN)	33
12.67.4.2 ~sequence()	34
12.67.5 Member Function Documentation	34
12.67.5.1 operator=(const sequence &rhs)	34
12.67.5.2 partial_assign(const sequence &rhs)	34
12.67.5.3 events()	34
12.67.5.4 events() const	34
12.67.5.5 any_selected_notes() const	34
12.67.5.6 triggerlist() const	34
12.67.5.7 triggerlist()	34
12.67.5.8 get_trigger_count() const	34
12.67.5.9 set_trigger_paste_tick(midipulse tick)	34
12.67.5.10get_trigger_paste_tick() const	34
12.67.5.11number() const	34
12.67.5.12number(int seqnum)	34
12.67.5.13modify()	34

12.67.5.14event_count() const
12.67.5.15set_hold_undo(bool hold)
12.67.5.16get_hold_undo() const
12.67.5.17set_have_undo()
12.67.5.18have_undo() const
12.67.5.19set_have_redo()
12.67.5.20have_redo() const
12.67.5.21push_undo(bool hold=false)
12.67.5.22pop_undo()
12.67.5.23pop_redo()
12.67.5.24push_trigger_undo()
12.67.5.25pop_trigger_undo()
12.67.5.26pop_trigger_redo()
12.67.5.27set_name(const std::string &name)
12.67.5.28set_name(char *name)
12.67.5.29set_measures(int lengthmeasures)
12.67.5.30get_measures()
12.67.5.31get_ppqn() const
12.67.5.32set_beats_per_bar(int beatspermeasure)
12.67.5.33get_beats_per_bar() const
12.67.5.34set_beat_width(int beatwidth)
12.67.5.35get_beat_width() const
12.67.5.36measures_to_ticks(int measures=1) const
12.67.5.37clocks_per_metronome(int cpm)
12.67.5.3&locks_per_metronome() const
12.67.5.39set_32nds_per_quarter(int tpq)
12.67.5.40get_32nds_per_quarter() const
12.67.5.41us_per_quarter_note(long upqn)
12.67.5.42us_per_quarter_note() const
12.67.5.43set_rec_vol(int rec_vol)

12.67.5.44set_song_mute(bool mute)
12.67.5.45toggle_song_mute()
12.67.5.46get_song_mute() const
12.67.5.47get_name() const
12.67.5.48name() const
12.67.5.49set_editing(bool edit)
12.67.5.50get_editing() const
12.67.5.51set_raise(bool edit)
12.67.5.52get_raise(void) const
12.67.5.53set_length(midipulse len, bool adjust_triggers=true) 537
12.67.5.54get_length() const
12.67.5.55get_last_tick()
12.67.5.56set_last_tick(midipulse tick)
12.67.5.57mod_last_tick()
12.67.5.5&et_playing(bool)
12.67.5.59get_playing() const
12.67.5.60toggle_playing()
12.67.5.61toggle_queued()
12.67.5.62off_queued()
12.67.5.63on_queued()
12.67.5.64get_queued() const
12.67.5.65get_queued_tick() const
12.67.5.66check_queued_tick(midipulse tick) const
12.67.5.67set_recording(bool)
12.67.5.68get_recording() const
12.67.5.69set_snap_tick(int st)
12.67.5.70set_quantized_rec(bool qr)
12.67.5.71get_quantized_rec() const
12.67.5.72set_thru(bool)
12.67.5.73get_thru() const

cii CONTENTS

12.67.5.74is_dirty_main()	540
12.67.5.75s_dirty_edit()	540
12.67.5.76s_dirty_perf()	540
12.67.5.77/s_dirty_names()	540
12.67.5.78set_dirty_mp()	540
12.67.5.79set_dirty()	541
12.67.5.80get_midi_channel() const	541
12.67.5.81is_smf_0() const	541
12.67.5.82set_midi_channel(midibyte ch)	541
12.67.5.83print() const	541
12.67.5.84print_triggers() const	541
12.67.5.85play(midipulse tick, bool playback_mode)	541
12.67.5.86add_event(const event &er)	541
12.67.5.87add_trigger(midipulse tick, midipulse len, midipulse offset=0, bool adjust_← offset=true)	542
12.67.5.8&split_trigger(midipulse tick)	542
12.67.5.89grow_trigger(midipulse tick_from, midipulse tick_to, midipulse len)	543
12.67.5.90del_trigger(midipulse tick)	543
12.67.5.91get_trigger_state(midipulse tick)	543
12.67.5.92select_trigger(midipulse tick)	543
12.67.5.93get_triggers() const	544
12.67.5.94unselect_triggers()	544
12.67.5.95ntersect_triggers(midipulse position, midipulse &start, midipulse &ender)	544
12.67.5.96ntersect_notes(midipulse position, midipulse position_note, midipulse &start, midipulse &ender, int ¬e)	544
12.67.5.97intersect_events(midipulse posstart, midipulse posend, midibyte status, midipulse &start)	545
12.67.5.98del_selected_trigger()	545
12.67.5.99cut_selected_trigger()	545
12.67.5.10@ppy_selected_trigger()	545
12.67.5.10pdaste_trigger(midipulse paste_tick=SEQ64_NO_PASTE_TRIGGER)	545

edit_t which=triggers::GROW_MOVE)	545
12.67.5.10 <u>Selected_trigger_start()</u>	546
12.67.5.104elected_trigger_end()	546
12.67.5.105fet_max_trigger()	546
12.67.5.106 ove_triggers(midipulse start_tick, midipulse distance, bool direction)	546
12.67.5.107 opy_triggers(midipulse start_tick, midipulse distance)	547
12.67.5.10@dear_triggers()	547
12.67.5.109et_trigger_offset() const	547
12.67.5.11 s et_midi_bus(char mb)	547
12.67.5.11get_midi_bus() const	547
12.67.5.1192et_master_midi_bus(mastermidibus *mmb)	547
12.67.5.11Select_note_events(midipulse tick_s, int note_h, midipulse tick_f, int note_← I, select_action_e action)	547
12.67.5.11stelect_events(midipulse tick_s, midipulse tick_f, midibyte status, midibyte cc, select_action_e action)	548
12.67.5.11 Select_events (midibyte status, midibyte cc, bool inverse=false)	548
12.67.5.11select_all_notes(bool inverse=false)	549
12.67.5.11get_num_selected_notes() const	549
12.67.5.11@et_num_selected_events(midibyte status, midibyte cc) const	549
12.67.5.11 se lect_all()	549
12.67.5.12@py_selected()	550
12.67.5.12dut_selected(bool copyevents=true)	550
12.67.5.122aste_selected(midipulse tick, int note)	550
12.67.5.129et_selected_box(midipulse &tick_s, int ¬e_h, midipulse &tick_f, int ¬e_l) .	551
12.67.5.12glet_clipboard_box(midipulse &tick_s, int ¬e_h, midipulse &tick_f, int ¬e_l)	551
12.67.5.125djust_timestamp(midipulse t, bool isnoteoff=false)	552
12.67.5.126 ip_timestamp(midipulse ontime, midipulse offtime)	552
12.67.5.127nove_selected_notes(midipulse deltatick, int deltanote)	552
12.67.5.128dd_note(midipulse tick, midipulse len, int note, bool paint=false)	553
12.67.5.129dd_event(midipulse tick, midibyte status, midibyte d0, midibyte d1, bool paint=false)	553

12.67.5.13stream_event(event &ev)
12.67.5.13dhange_event_data_range(midipulse tick_s, midipulse tick_f, midibyte status, midibyte cc, int d_s, int d_f)
12.67.5.1322crement_selected(midibyte status, midibyte) 55
12.67.5.13@ecrement_selected(midibyte status, midibyte)
12.67.5.13glrow_selected(midipulse deltatick)
12.67.5.13 Stretch_selected(midipulse deltatick)
12.67.5.13@move_marked()
12.67.5.13mark_selected()
12.67.5.13&emove_selected()
12.67.5.13\(\text{\text{9npaint_all}} \)
12.67.5.14@nselect()
12.67.5.14 <i>M</i> erify_and_link()
12.67.5.1412nk_new()
12.67.5.14&ero_markers()
12.67.5.14ølay_note_on(int note)
12.67.5.14 d ay_note_off(int note)
12.67.5.14@ff_playing_notes()
12.67.5.14 p ause()
12.67.5.14 (bool live_mode)
12.67.5.14% set_draw_marker()
12.67.5.15@set_draw_trigger_marker()
12.67.5.15get_next_note_event(midipulse *tick_s, midipulse *tick_f, int *note, bool *selected, int *velocity)
12.67.5.15@et_minmax_note_events(int &lowest, int &highest)
12.67.5.15@et_next_event(midibyte status, midibyte cc, midipulse *tick, midibyte *d0, midibyte *d1, bool *selected)
12.67.5.15glet_next_event(midibyte *status, midibyte *cc)
12.67.5.155et_next_trigger(midipulse *tick_on, midipulse *tick_off, bool *selected, midipulse *tick_offset)
12.67.5.15@uantize_events(midibyte status, midibyte cc, midipulse snap_tick, int divide, bool linked=false)

12.67.5.157ush_quantize(midibyte status, midibyte cc, midipulse snap_tick, int divide, bool linked=false)	561
12.67.5.158anspose_notes(int steps, int scale)	561
12.67.5.159ausical_key() const	561
12.67.5.16@nusical_key(int key)	561
12.67.5.161husical_scale() const	561
12.67.5.162busical_scale(int scale)	561
12.67.5.160ackground_sequence() const	561
12.67.5.164ackground_sequence(int bs)	561
12.67.5.165how_events() const	562
12.67.5.16@copy_events(const event_list &newevents)	562
12.67.5.167ote_off_margin() const	562
12.67.5.16ævent_in_range(const event &e, midibyte status, midipulse tick_s, midipulse tick f) const	562
12.67.5.169et_parent(perform *p)	562
12.67.5.17@ut_event_on_bus(event &ev)	563
12.67.5.17stet_trigger_offset(midipulse trigger_offset)	563
12.67.5.1722djust_trigger_offsets_to_length(midipulse newlen)	563
12.67.5.17adjust_offset(midipulse offset)	563
12.67.5.17#emove(event_list::iterator i)	563
12.67.5.17/5emove(event &e)	564
12.67.5.17@move_all()	564
12.67.5.176 hannel_match(const event &e) const	564
12.67.6 Friends And Related Function Documentation	564
12.67.6.1 perform	564
12.67.6.2 triggers	564
12.67.7 Field Documentation	564
12.67.7.1 m_events_clipboard	564
12.67.7.2 m_parent	564
12.67.7.3 m_events	565
12.67.7.4 m_triggers	565

12.67.7.5 m_events_undo_hold
12.67.7.6 m_have_undo
12.67.7.7 m_have_redo
12.67.7.8 m_events_undo
12.67.7.9 m_events_redo
12.67.7.10m_iterator_draw
12.67.7.11m_channel_match
12.67.7.12m_midi_channel
12.67.7.13m_bus
12.67.7.14m_song_mute
12.67.7.15m_notes_on
12.67.7.16m_masterbus
12.67.7.17m_playing_notes
12.67.7.18m_was_playing
12.67.7.19m_playing
12.67.7.20m_recording
12.67.7.21m_quantized_rec
12.67.7.22m_thru
12.67.7.23m_queued
12.67.7.24m_dirty_main
12.67.7.25m_dirty_edit
12.67.7.26m_dirty_perf
12.67.7.27m_dirty_names
12.67.7.28m_editing
12.67.7.29m_raise
12.67.7.30m_name
12.67.7.31m_last_tick
12.67.7.32m_queued_tick
12.67.7.33m_trigger_offset
12.67.7.34m_maxbeats

CONTENTS cvii

12.67.7.35m_ppqn	67
12.67.7.36m_seq_number	67
12.67.7.37m_length	67
12.67.7.38m_snap_tick	67
12.67.7.39m_time_beats_per_measure	67
12.67.7.40m_time_beat_width	67
12.67.7.41m_clocks_per_metronome	67
12.67.7.42m_32nds_per_quarter	67
12.67.7.43m_us_per_quarter_note	67
12.67.7.44m_rec_vol	67
12.67.7.45m_note_on_velocity	67
12.67.7.46m_note_off_velocity	68
12.67.7.47m_musical_key	68
12.67.7.48m_musical_scale	68
12.67.7.49m_background_sequence	68
12.67.7.50m_mutex	68
12.67.7.51m_note_off_margin	68
12.68seq64::trigger Class Reference	68
12.68.1 Detailed Description	69
12.68.2 Constructor & Destructor Documentation	69
12.68.2.1 trigger()	69
12.68.3 Member Function Documentation	69
12.68.3.1 operator<(const trigger &rhs)	69
12.68.3.2 length() const	70
12.68.3.3 tick_start() const	70
12.68.3.4 tick_start(midipulse s)	70
12.68.3.5 increment_tick_start(midipulse s)	70
12.68.3.6 decrement_tick_start(midipulse s)	70
12.68.3.7 tick_end() const	70
12.68.3.8 tick_end(midipulse e)	70

cviii CONTENTS

12.68.3.9 increment_tick_end(midipulse s)	. 570
12.68.3.10decrement_tick_end(midipulse s)	. 570
12.68.3.11offset() const	. 570
12.68.3.12offset(midipulse o)	. 570
12.68.3.13ncrement_offset(midipulse s)	. 570
12.68.3.14decrement_offset(midipulse s)	. 570
12.68.3.15selected() const	. 570
12.68.3.16selected(bool s)	. 570
12.68.4 Field Documentation	. 570
12.68.4.1 m_tick_start	. 570
12.68.4.2 m_tick_end	. 570
12.68.4.3 m_offset	. 570
12.68.4.4 m_selected	. 570
12.69seq64::triggers Class Reference	. 570
12.69.1 Member Typedef Documentation	. 573
12.69.1.1 List	. 573
12.69.1.2 Stack	. 573
12.69.2 Member Enumeration Documentation	. 573
12.69.2.1 grow_edit_t	. 573
12.69.3 Constructor & Destructor Documentation	. 573
12.69.3.1 triggers(sequence &parent)	. 573
12.69.3.2 ~triggers()	. 574
12.69.4 Member Function Documentation	. 574
12.69.4.1 operator=(const triggers &rhs)	. 574
12.69.4.2 set_ppqn(int ppqn)	. 574
12.69.4.3 set_length(int len)	. 574
12.69.4.4 triggerlist() const	. 574
12.69.4.5 triggerlist()	. 574
12.69.4.6 push_undo()	. 574
12.69.4.7 pop_undo()	. 574

12.69.4.8 pop_redo()	574
12.69.4.9 print(const std::string &seqname) const	574
12.69.4.10play(midipulse &starttick, midipulse &endtick)	574
12.69.4.11add(midipulse tick, midipulse len, midipulse offset=0, bool adjustoffset=true)	575
12.69.4.12adjust_offsets_to_length(midipulse newlen)	575
12.69.4.13split(midipulse tick)	576
12.69.4.14grow(midipulse tickfrom, midipulse tickto, midipulse length)	576
12.69.4.15remove(midipulse tick)	576
12.69.4.16get_state(midipulse tick)	576
12.69.4.17select(midipulse tick)	576
12.69.4.1&unselect()	577
12.69.4.19ntersect(midipulse position, midipulse &start, midipulse &end)	577
12.69.4.20remove_selected()	577
12.69.4.21copy_selected()	577
12.69.4.22paste(midipulse paste_tick=SEQ64_NO_PASTE_TRIGGER)	577
12.69.4.23move_selected(midipulse tick, bool adjustoffset, grow_edit_t which=GROW_M↔ OVE)	578
12.69.4.24get_selected_start()	578
12.69.4.25get_selected_end()	578
12.69.4.26get_maximum()	578
12.69.4.27move(midipulse starttick, midipulse distance, bool direction)	578
12.69.4.2©(midipulse starttick, midipulse distance)	579
12.69.4.29clear()	580
12.69.4.30next(midipulse *tick_on, midipulse *tick_off, bool *selected, midipulse *tick_offset)	580
12.69.4.31next_trigger()	580
12.69.4.32reset_draw_trigger_marker()	580
12.69.4.33set_trigger_paste_tick(midipulse tick)	580
12.69.4.34get_trigger_paste_tick() const	580
12.69.4.35adjust_offset(midipulse offset)	580
12.69.4.36split(trigger &trig, midipulse splittick)	581
12.69.5 Friends And Related Function Documentation	581

12.70.3.8 controller_active(int c) const	584
12.70.3.9 set_controller(int c, const std::string &cname, bool isactive)	584
12.70.3.10set_name(const std::string &instname)	584
12.70.3.11copy_definitions(const user_instrument &rhs)	585
12.70.4 Field Documentation	585
12.70.4.1 m_is_valid	585
12.70.4.2 m_controller_count	585
12.70.4.3 m_instrument_def	585
12.71seq64::user_instrument_t Struct Reference	585
12.71.1 Field Documentation	585
12.71.1.1 instrument	585
12.71.1.2 controllers	586
12.71.1.3 controllers_active	586
12.72seq64::user_midi_bus Class Reference	586
12.72.1 Detailed Description	587
12.72.2 Constructor & Destructor Documentation	587
12.72.2.1 user_midi_bus(const std::string &name="""")	587
12.72.2.2 user_midi_bus(const user_midi_bus &rhs)	587
12.72.3 Member Function Documentation	587
12.72.3.1 operator=(const user_midi_bus &rhs)	587
12.72.3.2 is_valid() const	587
12.72.3.3 set_defaults()	587
12.72.3.4 name() const	588
12.72.3.5 channel_count() const	588
12.72.3.6 channel_max() const	588
12.72.3.7 instrument(int channel) const	588
12.72.3.8 set_instrument(int channel, int instrum)	588
12.72.3.9 set_name(const std::string &name)	588
12.72.3.1@opy_definitions(const user_midi_bus &rhs)	588
12.72.4 Field Documentation	588

12.72.4.1 m_is_valid	39
12.72.4.2 m_channel_count	39
12.72.4.3 m_midi_bus_def	39
12.73seq64::user_midi_bus_t Struct Reference	39
12.73.1 Field Documentation	39
12.73.1.1 alias	39
12.73.1.2 instrument	39
12.74seq64::user_settings Class Reference	39
12.74.1 Detailed Description) 6
12.74.2 Member Typedef Documentation) 7
12.74.2.1 Busses) 7
12.74.2.2 BussIterator) 7
12.74.2.3 BussConstIterator) 7
12.74.2.4 Instruments) 7
12.74.2.5 InstrumentIterator) 7
12.74.2.6 InstrumentConstIterator) 7
12.74.3 Member Enumeration Documentation) 7
12.74.3.1 mainwid_grid_style_t) 7
12.74.4 Constructor & Destructor Documentation) 7
12.74.4.1 user_settings()) 7
12.74.4.2 user_settings(const user_settings &rhs)) 7
12.74.5 Member Function Documentation) 7
12.74.5.1 operator=(const user_settings &rhs)) 7
12.74.5.2 set_defaults()) 7
12.74.5.3 normalize()	98
12.74.5.4 add_bus(const std::string &alias)	98
12.74.5.5 add_instrument(const std::string &instname)	98
12.74.5.6 bus(int index)	98
12.74.5.7 instrument(int index)	98
12.74.5.8 bus_count() const	98

CONTENTS cxiii

12.74.5.9 set_bus_instrument(int index, int channel, int instrum)
12.74.5.10bus_instrument(int buss, int channel)
12.74.5.11bus_name(int buss)
12.74.5.12Instrument_count() const
12.74.5.13set_instrument_controllers(int index, int cc, const std::string &ccname, bool isactive)598
12.74.5.14instrument_name(int instrum)
12.74.5.15nstrument_name(int buss, int channel)
12.74.5.16nstrument_controller_active(int instrum, int cc)
12.74.5.17controller_active(int buss, int channel, int cc)
12.74.5.18nstrument_controller_name(int instrum, int cc)
12.74.5.19controller_name(int buss, int channel, int cc)
12.74.5.20grid_style() const
12.74.5.21grid_is_normal() const
12.74.5.22grid_is_white() const
12.74.5.23grid_is_black() const
12.74.5.24grid_brackets() const
12.74.5.25mainwnd_rows() const
12.74.5.26mainwnd_cols() const
12.74.5.27seqs_in_set() const
12.74.5.28gmute_tracks() const
12.74.5.29max_sets() const
12.74.5.30max_sequence() const
12.74.5.31text_x() const
12.74.5.32ext_y() const
12.74.5.33seqchars_x() const
12.74.5.34seqchars_y() const
12.74.5.35seqarea_x() const
12.74.5.36seqarea_y() const
12.74.5.37seqarea_seq_x() const
12.74.5.38seqarea_seq_y() const

12.74.5.39mainwid_border() const
12.74.5.40mainwid_spacing() const
12.74.5.41mainwid_x() const
12.74.5.42mainwid_y() const
12.74.5.43control_height() const
12.74.5.44zoom() const
12.74.5.45zoom(int value)
12.74.5.46global_seq_feature() const
12.74.5.47global_seq_feature(bool flag)
12.74.5.48seqedit_scale() const
12.74.5.49seqedit_scale(int scale)
12.74.5.50seqedit_key() const
12.74.5.51seqedit_key(int key)
12.74.5.52seqedit_bgsequence() const
12.74.5.53seqedit_bgsequence(int seqnum)
12.74.5.54use_new_font() const
12.74.5.55allow_two_perfedits() const
12.74.5.56perf_h_page_increment() const
12.74.5.57perf_v_page_increment() const
12.74.5.5&progress_bar_colored() const
12.74.5.59progress_bar_thick() const
12.74.5.6@nverse_colors() const
12.74.5.61window_redraw_rate() const
12.74.5.62save_user_config() const
12.74.5.63save_user_config(bool flag)
12.74.5.64grid_brackets(int thickness)
12.74.5.65grid_style(int gridstyle)
12.74.5.66mainwnd_rows(int value)
12.74.5.67mainwnd_cols(int value)
12.74.5.68max_sets(int value)

12.74.5.69(ext_x(int value)
12.74.5.70text_y(int value)
12.74.5.71seqchars_x(int value)
12.74.5.72seqchars_y(int value)
12.74.5.73seqarea_x(int value)
12.74.5.74seqarea_y(int value)
12.74.5.75seqarea_seq_x(int value)
12.74.5.76seqarea_seq_y(int value)
12.74.5.77mainwid_border(int value)
12.74.5.78mainwid_spacing(int value)
12.74.5.79control_height(int value)
12.74.5.80dump_summary()
12.74.5.81midi_ppqn() const
12.74.5.82midi_beats_per_bar() const
12.74.5.83midi_beats_per_minute() const
12.74.5.84midi_beat_width() const
12.74.5.85midi_buss_override() const
12.74.5.86min_zoom() const
12.74.5.87max_zoom() const
12.74.5.8&baseline_ppqn() const
12.74.5.89use_new_font(bool flag)
12.74.5.90allow_two_perfedits(bool flag)
12.74.5.91perf_h_page_increment(int inc)
12.74.5.92perf_v_page_increment(int inc)
12.74.5.93progress_bar_colored(int palcode)
12.74.5.94progress_bar_thick(bool flag)
12.74.5.95nverse_colors(bool flag)
12.74.5.96window_redraw_rate(int ms)
12.74.5.97midi_ppqn(int ppqn)
12.74.5.98midi_buss_override(char buss)

12.74.5.99midi_beats_per_bar(int beatsperbar)	603
12.74.5.10@idi_beats_per_minute(int beatsperminute)	603
12.74.5.101hidi_beat_width(int beatwidth)	603
12.74.5.10p2rivate_bus(int buss)	603
12.74.5.10parivate_instrument(int instrum)	603
12.74.6 Friends And Related Function Documentation	603
12.74.6.1 userfile	603
12.74.7 Field Documentation	603
12.74.7.1 m_midi_buses	603
12.74.7.2 m_instruments	603
12.74.7.3 m_grid_style	604
12.74.7.4 m_grid_brackets	604
12.74.7.5 m_mainwnd_rows	604
12.74.7.6 m_mainwnd_cols	604
12.74.7.7 m_max_sets	604
12.74.7.8 m_mainwid_border	604
12.74.7.9 m_mainwid_spacing	605
12.74.7.10m_control_height	605
12.74.7.11m_current_zoom	605
12.74.7.12m_global_seq_feature_save	605
12.74.7.13m_seqedit_scale	605
12.74.7.14m_seqedit_key	605
12.74.7.15m_seqedit_bgsequence	605
12.74.7.16m_use_new_font	606
12.74.7.17m_allow_two_perfedits	606
12.74.7.18m_h_perf_page_increment	606
12.74.7.19m_v_perf_page_increment	606
12.74.7.20m_progress_bar_colored	606
12.74.7.21m_progress_bar_thick	606
12.74.7.22m_inverse_colors	606

CONTENTS cxvii

12.74.7.23m_window_redraw_rate_ms	606
12.74.7.24m_text_x	607
12.74.7.25m_text_y	607
12.74.7.26m_seqchars_x	607
12.74.7.27m_seqchars_y	607
12.74.7.28m_midi_ppqn	607
12.74.7.29m_midi_beats_per_measure	607
12.74.7.30m_midi_beats_per_minute	607
12.74.7.31m_midi_beat_width	608
12.74.7.32m_midi_buss_override	608
12.74.7.33m_total_seqs	608
12.74.7.34m_seqs_in_set	608
12.74.7.35m_gmute_tracks	608
12.74.7.36m_max_sequence	608
12.74.7.37m_seqarea_x	608
12.74.7.38m_seqarea_y	608
12.74.7.39m_seqarea_seq_x	608
12.74.7.40m_seqarea_seq_y	609
12.74.7.41m_mainwid_x	609
12.74.7.42m_mainwid_y	609
12.74.7.43m_save_user_config	609
12.74.7.44mc_min_zoom	609
12.74.7.45mc_max_zoom	609
12.74.7.46mc_baseline_ppqn	609
12.75seq64::userfile Class Reference	610
12.75.1 Constructor & Destructor Documentation	611
12.75.1.1 userfile(const std::string &a_name)	611
12.75.1.2 ~userfile()	611
12.75.2 Member Function Documentation	611
12.75.2.1 parse(perform &a_perf)	611
12.75.2.2 write(const perform &a_perf)	611
12.75.2.3 dump_setting_summary()	611
Index	613

Chapter 1

Sequencer64

Author(s) Chris Ahlstrom 2015-11-27

1.1 Introduction

Sequencer64 is a major cleanup, refactoring, and documentation of the Seq24 live-play MIDI sequencer.

The current document, generated by Doxygen, describes the functions, classes, modules, and other entities used in this project.

Also read the ROADMAP, README, and contrib/bugs_to_investigate files to understand the genesis of this project and the things that still need to be done with Sequencer64.

Also, we have pretty deeply documented *Seq24* and *Sequencer64* with PDF files that can be generated by git-cloning the following projects, installing a number of tools related to PDF and LaTeX, and running "make":

- https://github.com/ahlstromcj/seg24-doc.git
- https://github.com/ahlstromcj/sequencer64-doc.git

These project also have prebuilt PDFs should one not want to bother building them.

In the present document, we've left out a fair amount of side-code to cut down on the size of the document. For example, the main module, redundant Windows support, utility headers like easy_macros.h, standard stuff like the mutex module, the fruity variants (at least the ones already refactored into their own modules), etc., are all left out. Still, the resulting PDF is over 300 pages long.

Some useful references:

- http://acad.carleton.edu/courses/musc108-00-f14/pages/04/04StandardMID← IFiles.html
- http://www.midimusicadventures.com/qs/midi-zips/soundtracks/kq6gm.zip

2 Sequencer64

Chapter 2

MIDI File Parsing in Sequencer64

Author(s) Chris Ahlstrom 2016-02-13

2.1 Introduction

This section describes the parsing of a MIDI file (and a few other topics). We wanted to add the reading of SMF 0 files to *Sequencer64*. We started with the main format that is supported, SMF 1. Once we understood that we, we figured out how to split a SMF 0 tracks correctly.

We split the midifile::parse() function into two sections. The first section analyzes the header of the MIDI. Then, based on whether the file is SMF 1 (the normal case) or SMF 0, either the parse_smf_1() function of or the parse—smf_0() function is called. The parse_smf_0() function creates one sequence object per channel present in the SMF 0 file, plus the original track. The last pattern slot (sequence 16) will contain the original track data, and the rest will contain common data and then channel data for each channel. After the parsing is done, all the tracks (including the original track) will be added to the performance. The user then has the option of deleting the original track, which will be the last track.

2.2 SMF 1 Parsing

This section describes the parsing of the header chunk, MThd, and the track chunk, MTrk.

The midifile::parse() function starts by opening the MIDI file, getting its file-size, pre-allocating the data vector to that size, reading all of the characters into that vector, and then closing the file.

2.2.1 MIDI File Header, MThd

The data of the header is read:

```
Header ID: "MThd" read_long() 4 bytes
MThd length: 6 read_long() 4 bytes
Format: 0, 1, 2 read_short() 2 bytes
No. of track: 1 or more read_short() 2 bytes
PPQN: 192 read_short() 2 bytes
```

The header ID and it's length are always the same values. The formats that Sequencer64 supports are 0 or 1. SMF 0 has only one track, while SMF 1 can support an arbitary number of tracks. The last value in the header is the PPQN value, which specifies the "pulses per quarter note", which is the basic time-resolution of events in the MIDI file. Common values are 96 or 192, but higher values are also common. Sequencer64 and its precursor, Seq24, default to 192.

2.2.2 MIDI Track, MTrk

Sequencer64 next reads the tracks specified in the file. Each track is assumed to cover a different MIDI channel, but always the same MIDI buss. (The MIDI buss is not a data item in standard MIDI files, but it is a special data item in Seq24/Sequencer64 MIDI files.) Each track is tagged by a standard chunk marker, "MTrk". Other markers are possible, and are to be ignored, if nothing else. Here are the values read at the beginning of a track:

```
Track ID: "MTrk" read_long() 4 bytes
Track length: varies read_long() 4 bytes
```

The track length is the number of bytes that need to be read in order to get all of the data in the track.

Next, a new sequence object is created, with the PPQN value passed to its constructor. The sequence then is hooked to the master MIDI buss object. The "RunningTime" accumulator is set to 0 for that track.

Next, the parse() function loops through the rest of the track, reading data and logging it to the sequence. Let's go through the loop, which is the meat of the processing.

TODO: An empty event is created before track processing, and re-used for every track and event. This seems dangerous. We moved the event constructor two levels of nesting deeper, and it seems to work fine.

Delta time. The amount time that passes from one event to the next is the *delta time*. For some events, the time doesn't matter, and is set to 0. This values is a *variable length value*, also known as a "VLV" or a "varinum". It provides a way of encoding arbitrarily large values, a byte at a time. For now, just note that a varinum is 1 or more bytes, and MIDI provides a way to tell when the varinum is complete.

```
Delta time: varies read_varinum() 1 or more bytes
```

2.2.2.1 Channel Events

Status. The byte after the delta time is examined by masking it against 0x80 to check the high bit. If not set, it is a "running status", it is replaced with the "last status", which is 0 at first.

```
Status byte: varies read_byte() 1 byte
```

If the high bit is set, it is a status, and is passed to the setter $event::set_status()$.

The "RunningTime" accumulator is incremented by the delta-time. The current time is adjusted as per the PPQN ratio, if needed, and passed to the setter $event::set_timestamp()$.

Now what does the status mean? First, the channel part of the status is masked out using the 0xF0 mask.

If it is a 2-data-byte event (note on, note off, aftertouch, control-change, or pitch-wheel), then the two data bytes are read:

```
Data byte 0: varies read_byte() 1 byte
Data byte 1: varies read_byte() 1 byte
```

If the status is a note-on event, with data[1] = 0, then it is converted to a note-off event, a fix for the output quirks of some MIDI devices, and the status of the event is amended to EVENT_NOTE_OFF.

If it is a 1-data-btye event (program change or channel pressure), then only data byte 0 is read.

Then the one or two data bytes are added to the event by overloads of event::set_data(), the event is added to the current sequence by sequence::add_event(), and the MIDI channel of the sequence is set by sequence::set_midi_channel().

Note that this is the point where parsing could detect a change in channel, and select a new sequence to support that channel, and add the events to that sequence, if the file were SMF 0.

Also note that the channel of the sequence is set every a new channel event/status is read. This should be done once, and then simply warned about if a non-matching channel occurs.

Lastly, note that it might be better to do the sequence function calls at the end of processing the event.

2.2 SMF 1 Parsing 5

2.2.2.2 Meta Events

If the event status masks off to 0xF0 (0xF0 to 0xFF), then it is a meta event. If the status is 0xFF, it is called a "Sequencer-specific", or "SeqSpec" event. For this kind of event, then a type byte and the length of the event are read.

```
Meta type: varies read_byte() 1 byte
Meta length: varies read_varinum() 1 or more bytes
```

If the type of the SeqSpec (0xFF) meta event is 0x7F, parsing checks to see if it is one of the Seq24 "proprietary" events. These events are tagged with various values that mask off to 0x24240000. The parser reads the tag:

```
Prop tag: 0x242400nn read_long() 4 bytes
```

These tags provide a way to save and recover Seq24/Sequencer64 properties from the MIDI file: MIDI buss, MIDI channel, time signature, sequence triggers, and (new), the key, scale, and background sequence to use with the track/sequence. Any leftover data for the tagged event is let go. Unknown tags ate skipped.

If the type of the SeqSpec (0xFF) meta event is 0x2F, then it is the End-of-Track marker. The current time is set using $sequence::set_length()$ and then $sequence::zero_markers()$ is called, and parsing is done for that track.

If the type of the SeqSpec (0xFF) meta event is 0x03, then it is the sequence name. The "length" number of bytes are read, and loaded by $sequence::set_name()$.

If the type of the SeqSpec (0xFF) meta event is 0x00, then it is the sequence number, which is read:

```
Seq number: varies read_short() 2 bytes
```

Note that the sequence number might be modified latter to account for the current screenset in force for a file import operation.

Anything other SeqSpec type is simply skipped by reading the "length" number of bytes.

To summarize the process, here are the relevant event and sequence setter calls typically made while parsing a MIDI track:

```
1. perform::add_sequence()
   (a) sequence::sequence()
   (b) sequence::set_master_midi_bus())
   (c) sequence::add_event()
        i. event::event()
        ii. event::set_status()
        iii. event::set_timestamp()
        iv. event::set_data()
   (d) sequence::set_midi_channel()
        (e) sequence::set_length()
        (f) sequence::set_name()
        (g) sequence::set_midi_bus()
2. xxxxx::yyyy()
```

2.2.3 Meta Events Summary

Here, we summarize the MIDI meta events for your edification.

```
1. FF 00 02 ssss: Sequence Number.
```

- 2. FF 01 len text: Text Event.
- 3. FF 02 len text: Copyright Notice.
- 4. FF 03 len text: Sequence/Track Name.
- 5. FF 04 len text: Instrument Name.
- 6. FF 05 len text: Lyric.
- 7. FF 06 len text: Marker.
- 8. FF 07 len text: Cue Point.
- 9. FF 08 len text: Patch/program Name.
- 10. FF 09 len text: Device Name.
- 11. FF 0A through 0F len text: Other kinds of text events.
- 12. FF 20 01 cc: MIDI channel (obsolete, used by Cakewalk)
- 13. FF 21 01 pp: MIDI port (obsolete, used by Cakewalk)
- 14. FF 2F 00: End of Track.
- 15. FF 51 03 tttttt: Set Tempo, us/qn.
- 16. FF 54 05 hr mn se fr ff: SMPTE Offset.
- 17. FF 58 04 nn dd cc bb: Time Signature.
- 18. FF 59 02 sf mi: Key Signature.
- 19. FF 7F len data: Sequencer-Specific.

The next sections describe the events that Sequencer tries to handle. These are

- Sequence Number (0x00)
- Track Name (0x03)
- End-of-Track (0x2F)
- Set Tempo (0x51) (Sequencer64 only)
- Time Signature (0x58) (Sequencer64 only)
- Sequencer-Specific (0x7F)
- System Exclusive (0xF0) Sort of handled, functionality incomplete..

2.2.3.1 Sequence Number (0x00)

```
FF 00 02 ss ss
```

This optional event must occur at the beginning of a track, before any non-zero delta-times, and before any transmittable MIDI events. It specifies the number of a sequence.

2.2 SMF 1 Parsing 7

2.2.3.2 Track/Sequence Name (0x03)

```
FF 03 len text
```

If in a format 0 track, or the first track in a format 1 file, the name of the sequence. Otherwise, the name of the track.

2.2.3.3 End of Track (0x2F)

```
FF 2F 00
```

This event is not optional. It is included so that an exact ending point may be specified for the track, so that it has an exact length, which is necessary for tracks which are looped or concatenated.

2.2.3.4 Set Tempo Event (0x51)

The MIDI Set Tempo meta event sets the tempo of a MIDI sequence in terms of the microseconds per quarter note. This is a meta message, so this event is never sent over MIDI ports to a MIDI device.

After the delta time, this event consists of six bytes of data:

```
FF 51 03 tt tt tt
```

Example:

```
FF 51 03 07 A1 20
```

- 1. 0xFF is the status byte that indicates this is a Meta event.
- 2. 0x51 the meta event type that signifies this is a Set Tempo event.
- 3. 0x03 is the length of the event, always 3 bytes.
- 4. The remaining three bytes carry the number of microseconds per quarter note. For example, the three bytes above form the hexadecimal value 0x07A120 (500000 decimal), which means that there are 500,000 microseconds per quarter note.

Since there are 60,000,000 microseconds per minute, the event above translates to: set the tempo to 60,000,000 / 500,000 = 120 quarter notes per minute (120 beats per minute). This is a 24-bit binary value, so each byte covers the full range of 0x00 to 0xFF.

This event normally appears in the first track. If not, the default tempo is 120 beats per minute. This event is important if the MIDI time division is specified in "pulses per quarter note", which does not itself define the length of the quarter note. The length of the quarter note is then determined by the Set Tempo meta event.

Representing tempos as time per beat instead of beat per time allows absolutely exact DWORD-term synchronization with a time-based sync protocol such as SMPTE time code or MIDI time code. This amount of accuracy provided by this tempo resolution allows a four-minute piece at 120 beats per minute to be accurate within 500 usec at the end of the piece.

We have now added the Tempo meta event (and the Time Signature meta event) to the track, which allows other sequencers to obtain these values from a Sequencer64 MIDI file. Here are the original headers for a normal MIDI file and its legacy (Seq24) conversion, as shown by the midicvt application:

```
hymne.asc
                                        hymne-ppqn-384.asc
MThd 1 4 96
                                        MThd 1 4 384
                                        MTrk
0 Meta SeqName "Vangelis: Hymne"
                                        0 SeqNr 0
0 TimeSig 4/4 24 8
                                        0 Meta SeqName "Vangelis: Hymne"
                                       0 SeqSpec 24 24 00 08 (no triggers)
0 SeqSpec 24 24 00 01 00 (MIDI buss 0)
0 Tempo 750000
0 Meta TrkEnd
                                        0 SeqSpec 24 24 00 06 04 04 (beats, width)
TrkEnd
                                        0 SeqSpec 24 24 00 02 00 (MIDI ch. 0)
                                        96 Meta TrkEnd
                                        TrkEnd
```

Here is the header data that result from the new conversion, which is used if the "legacy" option is not in force:

```
MThd 1 4 192
MTrk
0 SeqNr 0
0 Meta SeqName "Vangelis: Hymne"
0 TimeSig 4/4 24 8
0 Tempo 750000
0 SeqSpec 24 24 00 08
0 SeqSpec 24 24 00 01 00
0 SeqSpec 24 24 00 06 04 04
0 SeqSpec 24 24 00 02 00
48 Meta TrkEnd
TrkEnd
```

2.2.3.5 Time Signature Event (0x58)

After the delta time, this event consists of seven bytes of data:

```
FF 58 04 nn dd cc bb
```

The time signature is expressed as four numbers. nn and dd represent the numerator and denominator of the time signature as it would be notated. The numerator counts the number of beats in a measure (beats per measure or beats per bar). The denominator is a negative power of two: 2 represents a quarter-note, 3 represents an eighthnote, etc. The denominator specifies the unit of the beat (e.g. 4 or 8). In Seq24/Sequencer64, this value is also called the "beat width".

The CC parameter expresses the number of MIDI clocks (or "ticks", or "pulses") in a metronome click. The standard MIDI clock ticks 24 times per quarter note, so a value of 6 would mean the metronome clicks every 1/8th note. A CC value of 6 would mean that the metronome clicks once every 1/8th of a note (quaver). This MIDI clock is different from the clock (PPQN) that determines the start time and duration of the notes.

The bb parameter expresses the number of notated 32nd-notes in a MIDI quarter note (24 MIDI Clocks). The usual value for this parameter is 8, though some sequencers allow the user to specify that what MIDI thinks of as a quarter note, should be notated as something else. For example, a value of 16 means that the music plays two quarter notes for each quarter note metered out by the MIDI clock, so that the music plays at double speed.

Examples:

```
FF 58 04 04 02 18 08
```

- 1. 0xFF is the status byte that indicates this is a Meta event.
- 2. 0x58 the meta event type that signifies this is a Time Signature event.

2.2 SMF 1 Parsing 9

- 3. 0x04 is the length of the event, always 4 bytes.
- 4. 0x04 is the numerator of the time signature, and ranges from 0x00 to 0xFF.
- 5. 0x02 is the log base 2 of the denominator, and is the power to which 2 must be raised to get the denominator. Here, the denominator is 2 to 0x02, or 4, so the time signature is 4/4.
- 6. 0x18 is the metronome pulse in terms of the number of MIDI clock ticks per click. Assuming 24 MIDI clocks per quarter note, the value here (0x18 = 24) indidicates that the metronome will tick every 24/24 quarter note. If the value of the sixth byte were 0x30 = 48, the metronome clicks every two quarter notes, i.e. every half-note.
- 7. 0x08 defines the number of 32nd notes per beat. This byte is usually 8 as there is usually one quarter note per beat, and one quarter note contains eight 32nd notes.

A time signature of 6/8, with a metronome click every 3rd 1/8 note, would be encoded:

```
FF 58 04 06 03 24 08
```

Remember, a 1/4 note is 24 MIDI Clocks, therefore a bar of 6/8 is 72 MIDI Clocks. Hence 3 1/8 notes is 36 (=0x24) MIDI Clocks.

There should generally be a Time Signature Meta event at the beginning of a track (at time = 0), otherwise a default 4/4 time signature will be assumed. Thereafter they can be used to effect an immediate time signature change at any point within a track.

For a format 1 MIDI file, Time Signature Meta events should only occur within the first MTrk chunk.

If a time signature event is not present in a MIDI sequence, 4/4 signature is assumed.

In Sequencer64, the c_timesig SeqSpec event is given priority. The conventional time signature is used only if the c_timesig SeqSpec is not present in the file. NEEDS TO BE TESTED.

```
2.2.3.6 SysEx Event (0xF0)
```

If the meta event status value is 0xF0, it is called a "System-exclusive", or "SysEx" event.

```
F0 len data F7
```

Sequencer64 has some code in place to store these messages, but the data is currently not actually stored or used. Although there is some infrastructure to support storing the SysEx event within a sequence, the SysEx information is simply skipped. Sequencer64 warns if the terminating 0xF7 SysEx terminator is not found at the expected length. Also, some malformed SysEx events have been encountered, and those are detected and skipped as well.

2.2.3.7 Sequencer Specific (0x7F)

This data, also known as SeqSpec data, provides a way to encode information that a specific sequencer application needs, while marking it so that other sequences can safely ignore the information.

```
FF 7F len data
```

In *Seq24* and *Sequencer64*, the data portion starts with four bytes that indicate the kind of data for a particular SeqSpec event:

In Seq24, these events are placed at the end of the song, but are not marked as SeqSpec data. Most MIDI applications handle this situation fine, but some (e.g. midicvt) do not. Therefore, Sequencer64 makes sure to wrap each data item in the 0xFF 0x7F wrapper.

Also, the last three items above (key, scale, and background sequence) can also be stored (by *Sequencer64*) with a particular sequence/track, as well as at the end of the song. Not sure if this bit of extra flexibility is useful, but it is there.

2.2.3.8 Non-Specific End of Sequence

Any other statuses are deemed unsupportable in Sequencer64, and abort parsing with an error.

If the —bus option is in force, sequence::set_midi_bus() is called to override the buss number (if any) stored with the sequence.

Finally, $perform::add_sequence()$ adds the sequence to the encoded tune.

2.3 SMF 0 Parsing

After parsing SMF 1 track data, we end up with a number of sequences, each on a different MIDI channel. With SMF 0, data for all channels is present in a single track. Sequencer64 will read SMF 0 data, but we really need to be able to have one MIDI channel per track. So we need to take the data from the sequence and use it to make more sequences.

```
sequence::add_event().
sequence::set_midi_channel().
sequence::set_length().
sequence::set_midi_bus().
perform::add_sequence().
```

This code basically works. For now, please look at the source code for more details. Also, the reading of SMF 0 MIDI files is described in the *sequencer64-doc* project on GitHub.

2.4 Running Status

2.4 Running Status

When we apply the midicvt application to a file saved by Sequencer64, we can end up with a successful ASCII conversion that ends with an error message:

```
$ midicvt hymne-seq64.midi -o hymne-seq64.asc
? Error at MIDI file offset 12155 [0x2f7b]
Error: Garbage at end 'readtrack(): unexpected running status'
```

Is this a problem in midicvt or Sequencer4? Let's learn about running status.

Running status is a way to speed up the sending of MIDI bytes to a synthesizer or sequencer by taking advantage of redundancy where possible. For example, if we're sending a consecutive group of Note On and Note Off messages to a particular channel, we can save some time by not sending the channel status byte after the first time. Here's an example with Note On on channel 1:

```
0x90 3C 7F
0x90 40 7F
0x90 43 F3
```

Since no change in status occurs after the first of these three events, we can drop the subsequent status bytes:

```
0x90 3C 7F
40 7F
43 F3
```

The 0x90 byte is saved in a "running status buffer" (RSB), and is filled in by the receiving device.

Here is the sequence of events for operating with running status.

- 1. Clear the RSB buffer (RSB = 0) to start.
- 2. If a **Voice Category Status** (VCS) byte is received, then set RSB = VCS. VCS bytes range from 0x80 to 0xEF. This is binary 1000000 to 11100000.
- 3. If a data byte is received (data bytes range from 0x00 to 0x7F, binary 0000000 to 0111111; that is, bit 7 is always 0 in a data byte):
 - (a) If RSB != 0, first insert the RSB into the incoming data stream, then insert the data byte.
 - (b) If RSB == 0, then just insert the data byte into the incoming data stream.
- 4. Clear the RSB buffer (RSB = 0) when a System Common Message (SCM) status byte is received. SCM bytes range from 0xF0 to 0xF7.
- 5. The message after an SCM must begin with a status byte. That is a byte with bit 7 set.
- 6. Do no special action when a Realtime Category Message (RCM) byte is received. RCM bytes range from 0xF8 to 0xFF.

Note that some events, such as Tempo, assume that its bytes are all data bytes.

Chapter 3

JACK, Live, and Song Modes in Sequencer64

Author(s) Chris Ahlstrom 2016-08-18

3.1 Introduction

This section describes the interactions between JACK settings and the Live/Song Mode settings, with an eye to describing the proper behavior of Sequencer64 with JACK settings, how the Live/Song modes are supposed to work, and what bugs or issues remain in Sequencer64's JACK handling.

I'm not sure why Doxygen is applying the "code" font so often here. Weird, annoying.

3.2 JACK Functions

Please study the following URL and note these important points:

http://jackaudio.org/files/docs/html/transport-design.html

- The timebase master continuously updates position information, beats, timecode, etc. There is at most one
 master active at a time. If no client is registered as timebase master, frame numbers will be the only position
 information available.
- The timebase master registers a callback that updates position information while transport is rolling. Its output affects the following process cycle. This function is called immediately after the process callback in the same thread whenever the transport is rolling, or when any client has set a new position in the previous cycle.
- Clients that don't declare a sync callback are assumed ready immediately, anytime the transport wants to start. If a client doesn't require slow-sync processing, it can set its sync callback to NULL.
- The transport state is always valid; initially it is JackTransportStopped.
- When someone calls <code>jack_transport_start()</code>, the engine resets the poll bits and changes to a new state, <code>JackTransportStarting</code>.
- · When all slow-sync clients are ready, the state changes to JackTransportRolling.

Does Sequencer64 need a latency callback?

http://jackaudio.org/files/docs/html/group__ClientCallbacks.html

(We need to see why most of the following is in a monospaced font. Is there a new Doxygen feature?)

Here are summaries of the JACK functions used in the jack_assistant module:

3.2.1 jack_client_open()

```
Open a client session with a JACK server. More complex and powerful than <tt>jack_client_new()</tt>.

Clients choose which of several servers to connect, and how to start the server automatically, if not already running. There is also an option for JACK to generate a unique client name.

const char * client_name, jack_options_t options, jack_status_t * status,
```

client_name of at most jack_client_name_size() characters. The name scope is local to each server. Unless forbidden by the JackUseExactName option, the server will modify this name to create a unique variant, if needed.

options formed by OR-ing together JackOptions bits. Only the JackOpenOptions bits are allowed.

status (if non-NULL) an address for JACK to return information from the open operation. This status word is formed by OR-ing together the relevant JackStatus bits.

Optional parameters: depending on corresponding [options bits] additional parameters may follow status (in this order).

[JackServerName] (char *) server_name selects from among several possible concurrent server instances. Server names are unique to each user. If unspecified, use "default" unless \$JACK_DEFAULT_SERVER is defined in the process environment.

Returns:

Opaque client handle if successful. If this is NULL, the open operation failed, and *status includes JackFailure, and the caller is not a JACK client.

3.2.2 jack_on_shutdown()

Registers a function to call when the JACK server shuts down the client thread. It must be an asynchonrous POSIX signal handler: only async-safe functions, executed from another thread. A typical function might set a flag or write to a pipe so that the rest of the application knows that the JACK client thread has shut down. Clients do not need to call this function. It only helps clients understand what is going on. It should be called before <tt>jack_client_activate()</tt>.

3.2.3 jack_set_sync_callback()

Register/unregister as a slow-sync client; it can't respond immediately to transport position changes. The callback is run at the first opportunity after registration: if the client is active, this is the next process cycle, otherwise it is the first cycle after <tt>jack_activate()</tt>. After that, it runs as per JackSyncCallback rules. Clients that don't set this callback are assumed ready immediately any time the transport wants to start.

3.2 JACK Functions 15

3.2.4 jack_set_process_callback()

Tells the JACK server to call the callback whenever there is work. The function must be suitable for real-time execution, it cannot call functions that might block for a long time: malloc(), free(), printf(), pthread_mutex_lock(), sleep(), wait(), poll(), select(), pthread_join(), pthread_cond_wait(), etc. In the current class, this function is a do-nothing function.

3.2.5 jack set session callback()

Tells the JACK server to call the callback when a session event is delivered. Setting more than one session callback per process is probably a design error. For a multiclient application, it's more sensible to create a JACK client with only one session callback.

3.2.6 jack_activate()

Tells the JACK server that the application is ready to start processing.

3.2.7 jack release timebase()

TODO

3.2.8 jack client close()

TODO

3.2.9 jack_transport_start()

Starts the JACK transport rolling. Any client can make this request at any time. It takes effect no sooner than the next process cycle, perhaps later if there are slow-sync clients. This function is realtime-safe. No return code.

3.2.10 jack_transport_stop()

3.2.11 jack_transport_locate()

Repositions the transport to a new frame number. May be called at any time by any client. The new position takes effect in two process cycles. If there are slow-sync clients and the transport is already rolling, it will enter the JackTransportStarting state and begin invoking their sync_callbacks until ready. This function is realtime-safe.

3.2.12 jack_transport_reposition()

```
Request a new transport position. May be called at any time by any client. The new position takes effect in two process cycles. If there are slow-sync clients and the transport is already rolling, it will enter the JackTransportStarting state and begin invoking their sync_callbacks until ready. This function is realtime-safe. This call, made in the position() function, is currently disabled.
```

3.2.13 jack transport query()

Query the current transport state and position. This function is realtime-safe, and can be called from any thread. If called from the process thread, pos corresponds to the first frame of the current cycle and the state returned is valid for the entire cycle.

The first parameter is the client, which is a pointer to the JACK client structure.

The second parameter is a pointer to structure for returning current transport position; pos->valid will show which fields contain valid data. If pos is NULL, do not return position information.

This function returns the current transport state.

3.3 Modes Operation

3.3.1 No JACK, Live Mode

In ~/.config/sequencer64/sequencer64.rc, set:

- jack_transport = 0
- jack_master = 0
- jack master cond = 0
- song_start_mode = 0

By changing the start mode to 0 (false), Sequencer64 is put into Live Mode. With this setting, control of the muting and unmuting of patterns resides in the main window (the patterns window). One can start the playback in the performance (song) window, but it will not affect which patterns play, at all.

Note that this option is part of the File / Options / JACK/LASH configuration page.

3.3.2 No JACK, Song Mode

In \sim /.config/sequencer64/sequencer64.rc, set:

- jack_transport = 0
- jack master = 0
- jack_master_cond = 0
- song_start_mode = 1

By changing the start mode to 1 (true), Sequencer64 is put into Song Mode.

With this setting, control of the muting and unmuting of patterns resides in the song window (the performance window). The patterns shown in the pattern slots of the main window turn on and off whenever the progress bar is in the pattern as drawn in the perforance window.

Note that this option is part of the File / Options / JACK/LASH configuration page.

3.4 Breakage 17

3.3.3 JACK Transport

In ~/.config/sequencer64/sequencer64.rc, set:

- jack_transport = 1
- jack_master = 0
- jack master cond = 0
- song_start_mode = 0 or 1 (see previous section)

The current behavior is that gjackctl and sequencer64 playback/progress seem to be independent of each other.

The workaround seems to be to set seq24/sequencer64 as JACK Master, or if another application (e.g. Qtractor) is JACK Master.

OLD BEHAVIOR:

```
Start qjackctl, verify that it sets up correctly, then click it's
"play" button to start the transport rolling. Run sequencer64, load a
file. Then note that starting playback (whether in the main window or
in the performance window) is ineffective, but resets the time counter
in qjackctl. Why? With JACK sync enabled by the macro:

[JACK transport slave]
    jack sync(): zero frame rate [single report]!?

[JackTransportRolling]
```

[JackTransportStarting] (every time space bar pressed)

END OF OLD BEHAVIOR.

3.4 Breakage

Old message about seq24 being broken:

[Start playback]

 $\verb|http://lists.linuxaudio.org/pipermail/linux-audio-user/2010-November/073848. \leftarrow \verb|htm||$

```
i dont see the transport synchronisation working with a jackl svn version. you are still using only a sync callback.

and you are relying on the transport to go through the JackTransportStarting state.

this issue should be fixed.
iirc we came to the conclusion, that seq24 is broken, and we will not revert the changes in jack, which break it.

the quick and dirty fix on your side, would be to register an empty process_callback.

but the issue still remains. seq24 is NOT a slow sync client. but it registers a sync_callback.
and it even takes a lock in the sync callback.

the patch for jack-session support didnt get merged either.
```

Another one (no need for a URL):

I use seq24 for the majority of my projects but it isn't ideal (I should point out that I never finish anything). I don't like seq24's pianoroll editor, the way you do CC envelopes isn't ideal, it uses alsa-midi, there's unnecessary complexity in switching from pattern-trigger mode to song mode, and its insistence on being transport master while not even being able to adjust tempo when live is annoying

3.5 JACK References

- $\bullet \ \text{http://libremusicproduction.com/articles/demystifying-jack-\$E2\$80\$93-beginners-guidents.} \\$
- http://jackaudio.org/files/docs/html/transport-design.html
- http://kxstudio.linuxaudio.org/Repositories

Chapter 4

User Testing of Sequencer64 with Yoshimi

Author(s) Chris Ahlstrom 2016-03-04

4.1 Introduction

This section describes user testing of Sequencer64 using Yoshimi. It will expand as we work our way through all the many use-cases that can be achieved with Sequencer64 and Yoshimi.

Please note that the most advanced and recent testing can be found currently in the document contrib/notes/jack-testing txt. We will eventually merge the final tests here... someday.

4.2 Smoke Test

Every so often we run Sequencer64 with a software synthesizer to make sure we haven't broken any functionality via our major refactoring efforts. We call it a "smoke test". We fire up the two application, and see if anything smokes.

This smoke test sets up Yoshimi with a very simple ALSA setup, and no instruments are loaded. Instead, only the "Simple Sound" is used on all channels. We've been doing this test with Yoshimi 1.3.6. The current Debian Sid ("testing") version of Yoshimi is 1.3.6-2, pulled from SourceForge. It seems to have issues, so we've been cloning and pulling the code from:

```
https://github.com/Yoshimi/yoshimi.git
```

After getting the application build and installed, the next step is to run it, using ALSA for MIDI and for audio:

```
$ yoshimi -a -A &
```

Next, fix up the configuration files for Sequencer64, \sim /.config/sequencer64/sequencer64.rc and \sim /.config/sequencer64/sequencer64.usr.

First hide sequencer64.usr somewhere, or delete it, as it will determine what MIDI devices are available, and we don't want that (yet). Second, make sure that sequencer64.rc makes the following setting:

```
[manual-alsa-ports]
# Set to 1 if you want sequencer64 to create its own ALSA ports and
# not connect to other clients
0  # number of manual ALSA ports
```

Next, run the newly-built version of Sequencer64. If desired, use the –bus option described below to force the buss number to the buss you need, as shown in the second version of the command:

```
$ sequencer64/sequencer64 &
$ sequencer64/sequencer64 --bus 5 &
```

In File / Options / MIDI Clock, observe the MIDI inputs made available by your system. Our system shows:

```
[0] 14:0 (Midi Through Port-0)

[1] 128:0 (TiMidity port 0)

[2] 128:0 (TiMidity port 1)

[3] 128:0 (TiMidity port 2)

[4] 128:0 (TiMidity port 3)

[5] 129:0 (input)
```

For some reason (a bug in Yoshimi?), input "[5]" doesn't indicate that it is Yoshimi, but it is. Take note of that input number... that is the MIDI buss number that is needed to drive Yoshimi.

Also make sure that of the clock settings for those busses are "Off".

The next instruction still works, but it is easier to simply pass the option -bus 5 to Sequencer64 when starting it up.

Now open the file sequencer64/contrib/midi/b4uacuse-GM-format.midi in Sequencer64. For all of the patterns (slots) that have lots of data in them, right click on the pattern and select *Midi Bus / [5] 129:0 (input)* and the desired channel number. (Doesn't matter much, just use up the lower channel numbers first).

Back in Yoshimi, select each Part corresponding to the channels you selected. Make sure *Enabled* is checked for each desired channel.

Back in Sequencer64, click on each pattern you want to hear, which highlights them in black. Now click the play button (green triangle). The song should play, with each part using the "Simple Sound". Not too bad for a bunch of sine waves, eh?

Now we can test the application more fully. Note that the instructions here are very light. Detailed instructions on the usage of Sequencer64 can be found in the following project, which contains a PDF file and the LaTeX code used to build it:

```
https://github.com/ahlstromcj/sequencer64-doc.git
```

Although it applies to an earlier version of the project, it still mostly holds true for Sequencer64.

4.3 Tests in the Patterns Window

The Patterns window is the inside portion of the main window, supported by the mainwid class. it contains a grid of boxes or slots, with each slot potentially containing a pattern, sequence, or track. Empty tracks (i.e. tracks that contain no events, like title-only tracks) are highlighted in yellow.

This window supports only a single variant of mouse-handling.

4.3.1 Button Clicks on a Pattern

A left-click on a pattern slot should cause the following to happen:

- 1. The pattern will be highlighted (white on a black background). This won't occur until the button is released.
- 2. During playback, the pattern will emit MIDI events and play its sequence.
- 3. If the pattern is dragged to another slot, whether playing is in progress or not, releasing the button in the destination slot will move the pattern to that slot.

A right-click on a pattern slot should cause the following to happen:

- 1. If the pattern is empty, then a pop-up menu to make a New pattern, paste a pattern, or make other selections will appear.
- 2. If the pattern is active, then a pop-up menu to Edit the pattern or make other selections will appear.
- 3. A second right-click, just off the menu, will dismiss the menu.

4.3.2 Patterns Window Key Shortcuts

First, note the selection of the File / Options / Keyboard / Show keys option. The tests here should work whether or not it is selected. The only difference is if the keys are shown.

We got a segfault during this test, when we weren't being systematic about it.

4.3.3 The Sequencer64 User File

To be discussed.

4.4 Tests Using Valgrind

Valgrind is a very useful tool for unearthing memory issues and other issues in an application, especially when one has the source code and can build the code with debugging information.

One runs the application from the command line, preceding its command line with valgrind and some of its options.

4.4.1 Valgrind Suppressions

One problem with valgrind is that it also uncovers errors in system libraries that one has no control over. These errors clutter the output, so we suppress them using a valgrind "suppressions" file. Here's how to create one:

```
$ valgrind --gen-suppressions=yes --log-file=val.supp ./Sequencer64/sequencer64
$ valgrind --gen-suppressions=all --log-file=val.supp ./Sequencer64/sequencer64
```

As the program runs, one is asked to print a suppression. If the error is due to a system or third-party library, answer "Y return", and then copy-and-paste the suppression to a file, giving it a name. For example, we provide a file contrib/seq64.supp containing suppressions of errors that annoy us. There are way too many "errors" in ALSA, GTK+, gtkmm, glibc, and more.

The second command collects all the suppressions. Passing the val.supp file through sed makes it immediately usable:

```
$ sed -i -e /^==/g val.supp
```

Running valgrind like this then shows mostly the errors we care about:

```
$ valgrind --suppressions=val.supp ./Sequencer64/sequencer64
```

We've added some other suppression files to the contrib directory. Too much! For example:

```
https://github.com/dtrebbien/GNOME.supp
```

However, overall this process is very painful, and we're going to eventually do all the valgrind work on the unit-test project for Sequencer64:

```
https://github.com/ahlstromcj/seq64-tests
```

4.4.2 Full Valgrind Leak-Checking

Here's how to capture errors, while suppressing the system errors and while generating a log file:

```
$ valgrind --suppressions=contrib/seq64.supp --leak-check=full \
    --track-origins=yes --log-file=valgrind.log --show-leak-kinds=all \
    ./Sequencer64/sequencer64
```

The errors can be also be re-routed to a log-file via the "2> valgrind.log" shell redirection.

Another idea is to precede the valgrind command with the following construct:

```
$ G_SLICE=debug-blocks valgrind ...
```

G_SLICE=debug-blocks will turn off gtk's advanced memory management to allow valgrind to show correct results. This results in an amazing plethora or invalid read and invalid write errors in GNOME-related libraries. Sheesh!

And don't forget about Valgrind's "massif" memory-tracking tool! (More to come!)

4.4.2.1 Leak-Checking Basic Operation

For the first pass, just run Sequencer64, then immediately exit. Then scan the log file to see if any "errors" can be pinpointed to the application and library code.

Don't forget to run the same scenario without valgrind, in a console window, to see if any of our own debug/problem output occurs.

In any case, leakage tagged as "still reachable" isn't as bad as leakage tagged as "definitely lost" or "indirectly lost".

But good luck finding a Sequencer64 bug buried in the chaff of 3rd-party valgrind reports, even with some suppressions enabled. Apparently a lot of them have to do with data structures that are intended to last the full life of the application.

One can make the search a little easier by searching for the "seq64" namespace in the valgrind log.

4.5 Specific Fault Debugging

This section goes through specific debugging cases we encountered. They should be part of the regular testing of Sequencer64.

4.6 Snipping of a MIDI file.

In order to have a test file for the *seq64-tests* project, we loaded up the b4uacuse-GM-format.midi file, removed all but four of the tracks, and saved it as b4uacuse-snipped.midi. Loading this file into Sequencer64 caused the following:

```
$ ./Sequencer64/sequencer64
[Reading user configuration /home/ahlstrom/.config/sequencer64/sequencer64.usr]
[Reading rc configuration /home/ahlstrom/.config/sequencer64/sequencer64.rc]
get_sequence(): m_seqs[4] not null
Segmentation fault
```

First step, fire up a debugger and see what happened. We use cgdb, a text-based front-end for gdb with a "vi" feel.

```
$ cgdb ./Sequencer64/sequencer64
```

Just hit "r", do File / Open, navigate to b4uacuse-snipped.midi, select it, and watch what happens.

The "bt" (backtrace) command shows a pretty large stack, 52 items. Page up to the top of the stack, and select frame 1 ("fr 1"). This shows a mutex at a very low address, 0x650! Frame 2 shows we are in the automutex constructor, calling lock() on that same badly-located mutex. Frame 3 is in sequence::event_count(), same bad mutex, and the m_events member is at address 0x0. Obviously, we're dealing with an unallocated sequence.

Frame 4 is in mainwid::draw_sequence_on_pixmap(), just after we've retrieved the next sequence via perform ::get_sequence(4). But that would be the fifth sequence (the sequence numbers start at 0), and we snipped all but 4 from the file before we saved it.

So, one thing we need to do is *check* the value returned by get_sequence() before we try to use it. The other thing to do is figure out how we got to the fifth sequence, and fix that code as well. Using the command "p perf(). \leftarrow sequence_count()", we verify that there are indeed only 4 sequences allocated.

Frame 5 is in mainwid::draw_sequences_on_pixmap(). That function tries to load all sequences on the current screen-set, from 0 to 31, without checking to see how many their actually are. Inefficient and dangerous.

Frame 6 is in mainwid::reset(). We could pass perf().sequence_count() here for checking, or get it in mainwid ::draw_sequences_on_pixmap().

Before we fix this issue, we need to load a file that works, to see why it does not fail for most files. We will put a breakpoint at the top mainwid::draw_sequences_on_pixmap().

We hit the breakpoint before even loading a file, with a sequence_count() of 0. The call to valid_sequence(0) passes the test. We may want to make valid_sequence() take the sequence_count() into account. But the call to perf().is_active(0) prevents anything bad from happening at startup time.

Once we load a good file, the sequence_count() is 14 in mainwid::draw_sequences_on_pixmap(). We turn on the display of "offset" using the command "display offset", and "c" (for "continue") until offset = 14, which means we are beyond that last sequence. That bad access is prevented by perf().is active(14).

So the fundamental problem is that perf().is_active(4) is not protecting the access when we load the "bad file". We need to find and fix that issue before papering over the problem with better access checks.

Start again, putting a breakpoint in the call to "new sequence(m_ppqn)" in midifile. This call sets up some members and clears the list of 256 playing notes. Add another breakpoint at "a_perf.add_sequence()" to see what's happening there.

What we find is that the first two tracks have proper sequence numbers as read from the MIDI file, 0 and 1. But the third one preserves the number from the old file, 4. We have a disjunction between the track number and the sequence number, a conceptual problem. We can leave it as is, and beef up the error-checking, or replace the sequence number with the track number when loading the file. What to do?

- Make sure that the is-active flag for all sequences is "false", that the pointers are always null, and make sure to test both of these items (depending on context) before doing anything with the sequence.
- Convert the sequence number to the track number upon saving the MIDI file, or upon reading the MIDI file, and use that number when adding the sequence to the perform object. This might affect some seq24/sequencer64 functionality, however. It's big move.

We need information on reading and importing.

First, if we look at a file that we created long ago by importing b4uacuse.mid, b4uacuse-GM-format. \leftarrow midi, it has its fourteen sequence numbers identical to their track numbers. No problem.

Second, if we just read b4uacuse.mid, a non-seq24-created MIDI file, we see that each of its tracks have no sequence number – they are all zero. The perform::add_sequence() simple iterates from the beginning of m_seqs[] until it finds an inactive m_seqs[i], and uses that element to hold the sequence pointer.

But now it also segfaults! Let's fix all the non-checked get_sequence() calls right away, it is too big an issue to ignore.

In the end, we have to be aware that a screen-set can have blank (null) slots interspersed amongst the active slots.

Chapter 5

Licenses

Library This application and its libraries, sub-applications, and documents.

Author(s) Chris Ahlstrom 2015-09-10

5.1 License Terms for the This Project.

Wherever the tag \$XPC_SUITE_GPL_LICENSE\$ appears, or wherever reference to the GPL licensing scheme (any version) is mentioned, substitute the appropriate license text, depending on whether the project is a library, application, documentation, or server software. We're not going to include paragraphs of licensing information in every module; you are responsible for coming here to read the licensing information.

These licenses apply to each sub-project and file artifact in the project with which this license description was packaged.

Wherever the term **XPC** is encountered in this project, it refers to my projects, which go beyond the package that contains this document.

5.2 XPC Application License

The **XPC** application license is either the **GNU GPLv2**. or the **GNU GPLv3**. Generally, projects that originate with me use the latter language, while projects I have extended may specify the former license.

Copyright (C) 2015-2015 by Chris Ahlstrom

This program is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 3 of the License, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the

```
Free Software Foundation, Inc. 51 Franklin Street, Fifth Floor Boston, MA 02110-1301, USA.
```

The text of the GNU GPL version 3 license can also be found here:

```
http://www.gnu.org/licenses/gpl-3.0.txt
```

26 Licenses

5.3 XPC Library License

The XPC library license is the GNU LGPLv3.

Copyright (C) 2015-2015 by Chris Ahlstrom

This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 3 of the License, or (at your option) any later version.

This library is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Lesser Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with this library; if not, write to

```
Free Software Foundation, Inc. 51 Franklin Street, Fifth Floor Boston, MA 02110-1301, USA.
```

The text of the GNU LGPL version 3 license can also be found here:

```
http://www.gnu.org/licenses/lgpl-3.0.txt
```

5.4 XPC Documentation License

The XPC documentation license is the GNU FDLv1.3.

Copyright (C) 2015-2015 by Chris Ahlstrom

This documentation is free documentation; you can redistribute it and/or modify it under the terms of the GNU Free Documentation License as published by the Free Software Foundation; either version 1.3 of the License, or (at your option) any later version.

This documentation is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Free Documentation License for more details.

You should have received a copy of the GNU Free Documentation License along with this documentation; if not, write to the

```
Free Software Foundation, Inc. 51 Franklin Street, Fifth Floor Boston, MA 02110-1301, USA.
```

The text of the GNU FDL version 1.3 license can also be found here:

```
http://www.gnu.org/licenses/fdl.txt
```

5.5 XPC Affero License 27

5.5 XPC Affero License

The XPC "Affero" license is the GNU AGPLv3.

Copyright (C) 2015-2015 by Chris Ahlstrom

This server software is free server software; you can redistribute it and/or modify it under the terms of the GNU Affero General Public License as published by the Free Software Foundation; either version 1.3 of the License, or (at your option) any later version.

This documentation is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Free Documentation License for more details.

You should have received a copy of the GNU Affero General Public License along with this server software; if not, write to the

```
Free Software Foundation, Inc. 51 Franklin Street, Fifth Floor Boston, MA 02110-1301, USA.
```

The text of the GNU AGPL version 3 license can also be found here:

```
http://www.gnu.org/licenses/agpl-3.0.txt
```

At the present time, no XPC project uses the "Affero" license.

5.6 XPC License Summary

Include one of these licenses in your Doxygen documentation with one of the following Doxygen tags specified above:

```
\ref gpl_license_subproject
\ref gpl_license_application
\ref gpl_license_library
\ref gpl_license_documentation
\ref gpl_license_affero
```

For more information on navigating GNU licensing, see this page:

```
http://www.gnu.org/licenses/
```

Copies of these licenses (and some logos) are provided in the licenses directory of the main project (or you can search for them at *gnu.org*).

28 Licenses

Chapter 6

Todo List

File calculations.cpp

There are additional user-interface and MIDI scaling variables in the perfroll module that we need to move here.

File perfnames.cpp

When bringing up this dialog, and starting play from it, some extra horizontal lines are drawn for some of the sequences. This happens even in seq24, so this is long standing behavior. Is it useful, and how? Where is it done? In perfroll?

Global seq64::editable events::save events ()

Consider what to do about the sequence::m is modified flag.

Global seq64::eventedit::handle_save ()

Could also support writing the events to a new sequence, for added flexibility.

Global seq64::mainwid::timeout ()

We should use this callback to display the current time in the playback.

Global seq64::mainwnd::mainwnd (perform &p, bool allowperf2=true, int ppqn=SEQ64_USE_DEFAULT_← PPQN)

Offload most of the work into an initialization function like options does; make the perform parameter a reference; valgrind flags m_tooltips as lost data, but if we try to manage it ourselves, many more leaks occur.

Global seq64::mainwnd::on_key_release_event (GdkEventKey *ev)

Test this functionality in old and new application.

Global seq64::perfedit::perfedit (perform &p, bool second_perfedit=false, int ppqn=SEQ64_USE_DEFAU← LT_PPQN)

Offload most of the work into an initialization function like options does.

Global seq64::perform::add_sequence (sequence *seq, int perf)

Shouldn't we wrap around the sequence list if we can't find an empty sequence slot after prefnum?

This function needs some deeper analysis against the original, in my opinion.

Global seq64::perform::is_active (int seq) const

We should have the sequence object keep track of its own activity and access that via a reference or pointer.

Global seq64::perform::m seqs [c max sequence]

First, make the sequence array a vector, and second, put allof these flags into a structure and access those members indirectly.

Global seq64::perform::pop_trigger_undo ()

Look at seq32/src/perform.cpp and the perform::push_trigger_undo(track) function, which has a track parameter that has a -1 values the supports all tracks. It requires two new vectors (one for undo, one for redo), two new flags (likewise). We've put this code in place, macroed out.

30 Todo List

Global seq64::perform::set_left_tick (midipulse tick, bool setstart=true)

The perform::m_one_measure member is currently hardwired to PPQN * 4.

Global seq64::perfroll::set_ppqn (int ppqn)

Resolve the issue of c_perf_scale_x versus m_perf_scale_x in perfroll.

Global seq64::perftime::set_ppqn (int ppqn)

We need make the 4 constant variable per the number of beats (quarter-notes) per bar, and also at least make 16 (4x4) a meaningful manifest constant.

Global seq64::pulses_to_string (midipulse p)

Still needs to be unit tested.

Global seq64::pulses_to_timestring (midipulse p, const midi_timing &timinginfo)

Still needs to be unit tested.

Global seq64::seqdata::on_scroll_event (GdkEventScroll *ev)

DOCUMENT the segdata scrolling behavior in the documentation projects.

Global seq64::seqedit::get_measures ()

Create a sequence::set_units() function or a sequence::get_measures() function to forward to.

Global seq64::seqedit::seqedit (perform &perf, sequence &seq, int pos, int ppqn=SEQ64_USE_DEFAULT ← PPQN)

Offload most of the work into an initialization function like options does.

Support the hightlight feature in one or both perfedit windows in the same way it is done in the mainwid.

Global seq64::segmenu::m_modified

We need to make sure that the perform object is in control of the modification flag.

Global seg64::segmenu::seg_clear_perf()

All of seq_paste() can be offloaded to a (new) perform member function.

Global seq64::seqmenu::seq_copy ()

Can be offloaded to a perform member function that accepts a sequence clipboard non-const reference parameter.

Global seq64::segmenu::seg cut ()

A lot of seq_cut() can be offloaded to a (new) perform member function that takes a sequence clipboard non-const reference parameter.

Global seq64::seqmenu::seq_paste ()

All of seq_paste() can be offloaded to a (new) perform member function with a const clipboard reference parameter.

Global seq64::seqtime::update_pixmap ()

Sizing needs to be controlled by font parameters. Instead of 19 or 20, estimate the width of 3 letters. Instead of 9 pixels down, use the height of the seqtime and the height of a character.

Global seq64::sequence::get_minmax_note_events (int &lowest, int &highest)

For efficency, we should calculate this only when the event set changes, and save the results and return them if good.

Global seq64::sequence::stream_event (event &ev)

When we feel like debugging, we will replace the global is-playing call with the parent perform's is-running call.

Global seq64::triggers::next (midipulse *tick_on, midipulse *tick_off, bool *selected, midipulse *tick_← offset)

It would be a bit simpler to simply return a trigger object, wouldn't it?

Chapter 7

Deprecated List

Global seq64::clock_tick_duration_bogus (int bpm, int ppqn)

This is a somewhat bogus calculation used only for "statistical" output in the old perform module. Name changed to reflect this unfortunate fact. Use pulse_length_us() instead.

Global seq64::sequence::get_name () const

32 Deprecated List

Chapter 8

Namespace Index

	8.1	Namespace	List
--	-----	-----------	------

Here is a list of all namespaces with brief description	Н	ere	is	а	list	of	all	names	paces	with	brief	descri	ptions
---	---	-----	----	---	------	----	-----	-------	-------	------	-------	--------	--------

Gtk		 	 	 	 	??
seq64						
	Define this macro to use the new seq24 v	 	 	 	 	??

34 Namespace Index

Chapter 9

Hierarchical Index

9.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

seq64::AbstractPerfInput
seq64::FruityPerfInput
seq64::Seq24PerfInput
seq64::automutex
seq64::click
seq64::configfile
seq64::optionsfile
seq64::userfile
Dialog
seq64::options
DrawingArea
seq64::gui_palette_gtk2
seq64::gui_drawingarea_gtk2
seg64::eventslots
seq64::maintime
seq64::mainwid
seq64::perfnames
seq64::perfroll
seq64::perftime
seq64::seqdata
seq64::seqevent
seq64::seqkeys
seq64::seqroll
seq64::seqtime
seq64::editable_events
Entry
seq64::keybindentry
seq64::event
seq64::editable_event
seq64::event_list::event_key
seq64::event_list
seq64::font
seq64::FruitySeqEventInput
seq64::FruitySeqRollInput

36 Hierarchical Index

seq64::gui_assistant	172
seq64::gui_assistant_gtk2	174
seq64::jack_assistant	198
seq64::jack_scratchpad	213
seq64::jack_status_pair_t	214
seq64::keys_perform	217
seq64::keys_perform_gtk2	232
seq64::keys_perform_transfer	234
seq64::keystroke	236
seq64::lash	239
seq64::mastermidibus	272
seq64::midi_container	283
seq64::midi list	292
seq64::midi_vector	303
seq64::midi_control	289
seq64::midi measures	
seg64::midi splitter	
seq64::midi_timing	
· — •	306
•	312
·	329
seq64::condition_var	91
seq64::editable_event::name_value_t	
ObjectBase	500
seq64::seqmenu	491
seg64::mainwid	
seg64::perfnames	
seq64::perform	
	404
seq64::mainwnd	-
·	
	427
· ·	438
	439
seq64::Seq24SeqEventInput	442
seq64::Seq24SeqEventInput	442 523
seq64::Seq24SeqEventInputseq64::sequenceseq64::triggerseq64::triggerseq64::triggerseq64::triggerseq64::triggerseq64::triggerseq64::triggerseq64::triggerseq64::trigger	442 523 568
seq64::Seq24SeqEventInput seq64::sequence seq64::trigger seq64::triggers	442 523 568 570
seq64::Seq24SeqEventInput 4 seq64::sequence 8 seq64::trigger 8 seq64::triggers 8 seq64::user_instrument 8	442 523 568 570 582
seq64::Seq24SeqEventInput seq64::sequence seq64::trigger seq64::triggers seq64::user_instrument seq64::user_instrument_t	442 523 568 570 582 585
seq64::Seq24SeqEventInput seq64::sequence seq64::trigger seq64::triggers seq64::user_instrument seq64::user_instrument_t seq64::user_midi_bus	442 523 568 570 582 585 586
seq64::Seq24SeqEventInput seq64::sequence seq64::trigger seq64::triggers seq64::user_instrument seq64::user_instrument_t seq64::user_midi_bus seq64::user_midi_bus_t	442 523 568 570 582 585 586 589
seq64::Seq24SeqEventInput seq64::sequence seq64::trigger seq64::triggers seq64::user_instrument seq64::user_instrument_t seq64::user_midi_bus seq64::user_midi_bus_t seq64::user_settings	442 523 568 570 582 585 586
seq64::Seq24SeqEventInput seq64::sequence seq64::trigger seq64::triggers seq64::user_instrument seq64::user_instrument_t seq64::user_midi_bus seq64::user_midi_bus_t seq64::user_settings Window	442 523 568 570 582 585 586 589 589
seq64::Seq24SeqEventInput seq64::sequence seq64::trigger seq64::triggers seq64::user_instrument seq64::user_instrument_t seq64::user_midi_bus seq64::user_midi_bus_t seq64::user_settings Window seq64::gui_window_gtk2	442 523 568 570 582 585 586 589 589
seq64::Seq24SeqEventInput seq64::sequence seq64::trigger seq64::triggers seq64::user_instrument seq64::user_instrument_t seq64::user_midi_bus seq64::user_midi_bus_t seq64::user_settings Window seq64::gui_window_gtk2 seq64::eventedit	442 523 568 570 582 585 586 589 589
seq64::Seq24SeqEventInput seq64::sequence seq64::trigger seq64::user_instrument seq64::user_instrument_t seq64::user_midi_bus seq64::user_midi_bus_t seq64::user_settings Window seq64::gui_window_gtk2 seq64::eventedit seq64::Ifownd	442 523 568 570 582 585 586 589 195 135 241
seq64::Seq24SeqEventInput seq64::sequence seq64::trigger seq64::user_instrument seq64::user_instrument_t seq64::user_midi_bus seq64::user_midi_bus_t seq64::user_settings Window seq64::gui_window_gtk2 seq64::eventedit seq64::lfownd seq64::mainwnd	442 523 568 570 582 585 586 589 195 135 241 259
seq64::Seq24SeqEventInput seq64::sequence seq64::trigger seq64::user_instrument seq64::user_instrument_t seq64::user_midi_bus seq64::user_midi_bus_t seq64::user_settings Window seq64::gui_window_gtk2 seq64::eventedit seq64::Ifownd	442 523 568 570 582 585 586 589 195 135 241 2259 337

Chapter 10

Data Structure Index

10.1 Data Structures

Here are the data structures with brief descriptions:

seq64::AbstractPerfInput	
Provides an abstract base class to provide the minimal interface for the various "perf input"	
classes	??
seq64::automutex	
Provides a mutex that locks automatically when created, and unlocks when destroyed	??
seq64::click	
Encapsulates any possible mouse click	??
seq64::condition_var	
A mutex works best in conjunction with a condition variable	??
seq64::configfile	
This class is the abstract base class for optionsfile and userfile	??
seq64::editable_event	
Provides for the management of MIDI editable events	??
seq64::editable_events	•
Provides for the management of an ordered collection MIDI editable events	??
seq64::event	~
Provides events for management of MIDI events	??
seq64::event_list::event_key	??
Provides a key value for an event map	
seq64::event_list Receptable for MIDI events	??
seq64::eventedit	
This class supports an Event Editor that is used to tweak the details of events and get a better	
idea of the mix of events in a sequence	??
seq64::eventslots	•
This class implements the left-side list of events in the pattern event-edit window	??
seq64::font	
This class provides a wrapper for rendering fonts that are encoded as a 16 x 16 pixmap file in	
XPM format	??
seq64::FruityPerfInput	
Implements the performance input of that certain fruity sequencer that people seem to like	??
seq64::FruitySeqEventInput	
This structure implements the interaction methods for the "fruity" mode of operation	??
seq64::FruitySeqRollInput	
Implements the fruity mouse interaction paradigm for the segroll	22

38 Data Structure Index

seq64::gui assistant	
This class provides an interface for some of the GUI support needed in Sequencer64	??
seq64::gui_assistant_gtk2 This class provides an interface for some of the Gtk/Gdk/Glib support needed in Sequencer64	4 ??
seq64::gui_drawingarea_gtk2 Implements the basic drawing areas of the application	??
seq64::gui_palette_gtk2	
Implements a stock palette of Gdk::Color elements	??
This class supports a basic interface for Gtk::Window-derived objects	??
seq64::jack_assistant This class provides the performance mode JACK support	??
seq64::jack_scratchpad Provide a temporary structure for passing data and results between a perform and jack_assista object	
seq64::jack_status_pair_t	
Provides an internal type to make it easier to display a specific and accurate human-readal message when a JACK operation fails	
seq64::keybindentry Class for management of application key-bindings	??
seq64::keys_perform This class supports the performance mode	??
seq64::keys_perform_gtk2	??
This class supports the performance mode	
Provides a data-transfer structure to make it easier to fill in a keys_perform object's member using sscanf()	ers ??
seq64::keystroke Encapsulates any practical keystroke	??
seq64::lash	
This class supports LASH operations, if compiled with LASH support (i.e seq64::lfownd	??
One LFO window class	??
This class provides the drawing of the progress bar at the top of the main window, along with to "pills" that move in time with the beat and measure	wo ??
seq64::mainwid This class implements the piano roll area of the application	??
seq64::mainwnd This class implements the functionality of the main window of the application, except for t Patterns Panel functionality, which is implemented in the mainwid class	
seq64::mastermidibus The class that "supervises" all of the midibus objects?	??
seq64::midi_container This class is the abstract base class for a container of MIDI track information	
seq64::midi_control	
This class (formerly a struct) contains the control information for sequences that make up a li set	
seq64::midi_list This class is the std::list implementation of the midi_container	??
seq64::midi_measures	
Provides a data structure to hold the numeric equivalent of the measures string "measures :beats:divisions" ("m:b:d")	
seq64::midi_splitter This class handles the parsing and writing of MIDI files	??
seq64::midi_timing We anticipate the need to have a small structure holding the parameters needed to calcula MIDI times within an arbitrary song	
. · ·	

10.1 Data Structures 39

seq64::midi_vector	
This class is the std::vector implementation of the midi_container	??
seq64::midibus Provides a class for handling the MIDI buss on Linux	??
seq64::midifile	
This class handles the parsing and writing of MIDI files	??
seq64::mutex	
Simple wrapper for the pthread_mutex_t type used as a recursive mutex	??
seq64::editable_event::name_value_t	
Provides a type that contains the pair of values needed for the various lookup maps that are	
needed to manage editable events	??
seq64::options	
This class supports a full tabbed options dialog	??
seq64::optionsfile	00
Provides a file for reading and writing the application' main configuration file	??
seq64::perfedit	
This class supports a Performance Editor that is used to arrange the patterns/sequences defined	22
in the patterns panel	??
seq64::perfnames	22
This class implements the left-side keyboard in the patterns window	??
seq64::perform This class supports the performance mode	??
seq64::performcallback	11
Provides for notification of events	??
seq64::perfroll	• •
This class implements the performance roll user interface	??
seq64::perftime	• •
This class implements drawing the piano time at the top of the "performance window" (the "song	
editor")	??
seq64::rc_settings	
This class contains the options formerly named "global_xxxxxx"	??
seq64::rect	
A small helper class representing a rectangle	??
seq64::gui_drawingarea_gtk2::rect	
A small helper structure representing a rectangle	??
seq64::Seq24PerfInput	
Implements the default (Seq24) performance input characteristics of this application	??
seq64::Seq24SeqEventInput	
This structure implement the normal interaction methods for Seq24	??
seq64::seqdata	
This class supports drawing piano-roll eventis on a window	??
seq64::seqedit	
Implements the Pattern Editor, which has references to:	??
seq64::seqevent	
Implements the piano event drawing area	??
seq64::seqkeys	
This class implements the left side piano of the pattern/sequence editor	??
seq64::seqmenu	
This class handles the right-click menu of the sequence slots in the pattern window	??
seq64::seqroll	
Implements the piano roll section of the pattern editor	??
seq64::seqtime	
This class implements the piano time, whatever that is	??
seq64::sequence	
Firstly a receptable for a single track of MIDI data read from a MIDI file or edited into a pattern	??
seq64::trigger	
This class hold a single trigger for a sequence object	??

40 Data Structure Index

seq64::triggers	
Receptable the triggers that can be used with a sequence object	??
seq64::user_instrument	
Provides data about the MIDI instruments, readable from the "user" configuration file	??
seq64::user_instrument_t	
This structure corresponds to [user-instrument-N] definitions in the \sim /.seq24usr	
<pre>or ~/.config/sequencer64/sequencer64.usr file</pre>	??
seq64::user_midi_bus	
Provides data about the MIDI busses, readable from the "user" configuration file	??
seq64::user_midi_bus_t	
This structure corresponds to [user-midi-bus-0] definitions in the \sim /.seq24usr	
("user") file (\sim /.config/sequencer64/sequencer64.usr in the latest version of the	
application)	??
seq64::user_settings	
Holds the current values of sequence settings and settings that can modify the number of se-	
quences and the configuration of the user-interface	??
seq64::userfile	
Supports the user's \sim /.config/sequencer64/sequencer64.usr and \sim /.seq24us	sr
configuration file	22

Chapter 11

Namespace Documentation

11.1 Gtk Namespace Reference

11.2 seq64 Namespace Reference

Define this macro to use the new seq24 v.

Data Structures

class AbstractPerfInput

Provides an abstract base class to provide the minimal interface for the various "perf input" classes.

· class automutex

Provides a mutex that locks automatically when created, and unlocks when destroyed.

· class click

Encapsulates any possible mouse click.

· class condition_var

A mutex works best in conjunction with a condition variable.

· class configfile

This class is the abstract base class for optionsfile and userfile.

class editable_event

Provides for the management of MIDI editable events.

class editable_events

Provides for the management of an ordered collection MIDI editable events.

· class event

Provides events for management of MIDI events.

· class event_list

The event_list class is a receptable for MIDI events.

· class eventedit

This class supports an Event Editor that is used to tweak the details of events and get a better idea of the mix of events in a sequence.

· class eventslots

This class implements the left-side list of events in the pattern event-edit window.

class font

This class provides a wrapper for rendering fonts that are encoded as a 16 x 16 pixmap file in XPM format.

class FruityPerfInput

Implements the performance input of that certain fruity sequencer that people seem to like.

struct FruitySeqEventInput

This structure implements the interaction methods for the "fruity" mode of operation.

class FruitySeqRollInput

Implements the fruity mouse interaction paradigm for the seqroll.

· class gui assistant

This class provides an interface for some of the GUI support needed in Sequencer64.

class gui_assistant_gtk2

This class provides an interface for some of the Gtk/Gdk/Glib support needed in Sequencer64.

class gui_drawingarea_gtk2

Implements the basic drawing areas of the application.

· class gui_palette_gtk2

Implements a stock palette of Gdk::Color elements.

· class gui_window_gtk2

This class supports a basic interface for Gtk::Window-derived objects.

· class jack assistant

This class provides the performance mode JACK support.

class jack_scratchpad

Provide a temporary structure for passing data and results between a perform and jack_assistant object.

· struct jack status pair t

Provides an internal type to make it easier to display a specific and accurate human-readable message when a JACK operation fails.

class keybindentry

Class for management of application key-bindings.

class keys_perform

This class supports the performance mode.

class keys_perform_gtk2

This class supports the performance mode.

struct keys_perform_transfer

Provides a data-transfer structure to make it easier to fill in a keys perform object's members using sscanf().

· class keystroke

Encapsulates any practical keystroke.

class lash

This class supports LASH operations, if compiled with LASH support (i.e.

· class Ifownd

One LFO window class.

class maintime

This class provides the drawing of the progress bar at the top of the main window, along with two "pills" that move in time with the beat and measure.

· class mainwid

This class implements the piano roll area of the application.

· class mainwnd

This class implements the functionality of the main window of the application, except for the Patterns Panel functionality, which is implemented in the mainwid class.

· class mastermidibus

The class that "supervises" all of the midibus objects?

class midi_container

This class is the abstract base class for a container of MIDI track information.

· class midi control

This class (formerly a struct) contains the control information for sequences that make up a live set.

· class midi_list

This class is the std::list implementation of the midi_container.

· class midi measures

Provides a data structure to hold the numeric equivalent of the measures string "measures:beats:divisions" ("m:b:d").

class midi_splitter

This class handles the parsing and writing of MIDI files.

· class midi_timing

We anticipate the need to have a small structure holding the parameters needed to calculate MIDI times within an arbitrary song.

· class midi_vector

This class is the std::vector implementation of the midi_container.

· class midibus

Provides a class for handling the MIDI buss on Linux.

· class midifile

This class handles the parsing and writing of MIDI files.

· class mutex

The mutex class provides a simple wrapper for the pthread_mutex_t type used as a recursive mutex.

· class options

This class supports a full tabbed options dialog.

· class optionsfile

Provides a file for reading and writing the application' main configuration file.

· class perfedit

This class supports a Performance Editor that is used to arrange the patterns/sequences defined in the patterns panel.

class perfnames

This class implements the left-side keyboard in the patterns window.

· class perform

This class supports the performance mode.

· struct performcallback

Provides for notification of events.

· class perfroll

This class implements the performance roll user interface.

· class perftime

This class implements drawing the piano time at the top of the "performance window" (the "song editor").

class rc_settings

This class contains the options formerly named "global_xxxxxx".

· class rect

A small helper class representing a rectangle.

class Seq24PerfInput

 ${\it Implements the default (Seq 24) performance input characteristics of this application.}$

• struct Seq24SeqEventInput

This structure implement the normal interaction methods for Seq24.

· class seqdata

This class supports drawing piano-roll eventis on a window.

· class segedit

Implements the Pattern Editor, which has references to:

· class seqevent

Implements the piano event drawing area.

· class segkeys

This class implements the left side piano of the pattern/sequence editor.

class segmenu

This class handles the right-click menu of the sequence slots in the pattern window.

class segroll

Implements the piano roll section of the pattern editor.

· class segtime

This class implements the piano time, whatever that is.

· class sequence

The sequence class is firstly a receptable for a single track of MIDI data read from a MIDI file or edited into a pattern.

· class trigger

This class hold a single trigger for a sequence object.

· class triggers

The triggers class is a receptable the triggers that can be used with a sequence object.

· class user_instrument

Provides data about the MIDI instruments, readable from the "user" configuration file.

· struct user_instrument_t

This structure corresponds to [user-instrument-N] definitions in the \sim /.seq24usr or \sim /.config/sequencer64/sequencer file.

· class user midi bus

Provides data about the MIDI busses, readable from the "user" configuration file.

· struct user_midi_bus_t

This structure corresponds to [user-midi-bus-0] definitions in the \sim /.seq24usr ("user") file (\sim /.config/sequencer64/sequencer64.usr in the latest version of the application).

class user_settings

Holds the current values of sequence settings and settings that can modify the number of sequences and the configuration of the user-interface.

· class userfile

Supports the user's \sim /.config/sequencer64/sequencer64.usr and \sim /.seq24usr configuration file.

Typedefs

• typedef unsigned char midibyte

Provides a fairly common type definition for a byte value.

· typedef unsigned char bussbyte

Distinguishes a buss/bus number from other MIDI bytes.

· typedef unsigned short midishort

Distinguishes a short value from the unsigned short values implicit in short-valued MIDI numbers.

typedef unsigned long midilong

Distinguishes a long value from the unsigned long values implicit in long-valued MIDI numbers.

· typedef long midipulse

Distinguishes a long value from the unsigned long values implicit in MIDI time measurements.

Enumerations

Functions

bool extract_timing_numbers (const std::string &s, std::string &part_1, std::string &part_2, std::string &part ← 3, std::string &fraction)

Extracts up to 4 numbers from a colon-delimited string.

• std::string pulses to string (midipulse p)

Converts MIDI pulses (also known as ticks, clocks, or divisions) into a string.

• std::string pulses_to_measurestring (midipulse p, const midi_timing &seqparms)

Converts a MIDI pulse/ticks/clock value into a string that represents "measures:beats:ticks" ("measures:beats⇔:division").

bool pulses_to_midi_measures (midipulse p, const midi_timing &seqparms, midi_measures &measures)

Converts a MIDI pulse/ticks/clock value into a string that represents "measures:beats:ticks" ("measures:beats⇔:division").

• std::string pulses_to_timestring (midipulse p, int bpm, int ppqn)

Converts a MIDI pulse/ticks/clock value into a string that represents "hours:minutes:seconds.fraction".

• std::string pulses_to_timestring (midipulse p, const midi_timing &timinginfo)

Converts a MIDI pulse/ticks/clock value into a string that represents "hours:minutes:seconds.fraction".

midipulse measurestring_to_pulses (const std::string &measures, const midi_timing &seqparms)

Converts a string that represents "measures:beats:division" to a MIDI pulse/ticks/clock value.

midipulse midi_measures_to_pulses (const midi_measures &measures, const midi_timing &seqparms)

Converts a string that represents "measures:beats:division" to a MIDI pulse/ticks/clock value.

• midipulse timestring_to_pulses (const std::string ×tring, int bpm, int ppqn)

Converts a string that represents "hours:minutes:seconds.fraction" into a MIDI pulse/ticks/clock value.

• midipulse string_to_pulses (const std::string &s, const midi_timing &mt)

Converts a time string to pulses.

midibyte string_to_midibyte (const std::string &s)

Converts a string to a MIDI byte.

• std::string shorten file spec (const std::string &fpath, int leng)

Shortens a file-specification to make sure it is no longer than the provided length value.

bool string not void (const std::string &s)

Tests that a string is not empty and has non-space characters.

bool string_is_void (const std::string &s)

Tests that a string is empty or has only white-space characters.

bool strings_match (const std::string &target, const std::string &x)

Compares two strings for a form of semantic equality, for the purposes of editable_event(), for example.

int log2_time_sig_value (int tsd)

Calculates the log-base-2 value of a number that is already a power of 2.

void tempo_us_to_bytes (midibyte t[3], int tempo_us)

Provide a way to convert a tempo value (microseconds per quarter note) into the three bytes needed as value in a Tempo meta event.

int zoom_power_of_2 (int ppqn)

Calculates a suitable starting zoom value for the given PPQN value.

double beats_per_minute_from_tempo_us (double tempous)

This function calculates the effective beats-per-minute based on the value of a Tempo meta-event.

double tempo_us_from_beats_per_minute (double bpm)

This function is the inverse of beats_per_minute_from_tempo().

long tempo_to_us (int bpm)

Converts tempo (e.g.

• double pulse_length_us (int bpm, int ppqn)

Calculates pulse-length from the BPM (beats-per-minute) and PPQN (pulses-per-quarter-note) values.

• double delta time us to ticks (unsigned long us, int bpm, int ppqn)

Converts delta time in microseconds to ticks.

double ticks_to_delta_time_us (midipulse delta_ticks, int bpm, int ppqn)

Converts the time in ticks ("clocks") to delta time in microseconds.

double clock_tick_duration_bogus (int bpm, int ppqn)

Calculates the duration of a clock tick based on PPQN and BPM settings.

• int clock ticks from ppqn (int ppqn)

A simple calculation to convert PPQN to MIDI clock ticks.

double double_ticks_from_ppqn (int ppqn)

A simple calculation to convert PPQN to MIDI clock ticks.

midipulse pulses_per_measure (int ppqn=SEQ64_DEFAULT_PPQN)

Calculates the pulses per measure.

midipulse measures_to_ticks (int bpm, int ppqn, int bw, int measures=1)

Calculates the length of an integral number of measures, in ticks.

double wave_func (double angle, wave_type_t wavetype)

Calculates a wave function for use as an LFO (low-frequency oscillator) for modifying data values in a sequence.

• bool help_check (int argc, char *argv[])

Checks to see if the first option is a help or version argument, just so we can skip the "Reading configuration ..." messages.

• bool parse options files (perform &p, int argc, char *argv[])

Provides the command-line option support, as well as some setup support, extracted from the main routine of Sequencer64.

• int parse_command_line_options (int argc, char *argv[])

Parses the command-line options on behalf of the application.

bool write options files (const perform &p)

Saves all options to the "rc" and "user" configuration files.

std::string build_details ()

Generates a string describing the features of the build.

• std::string to_string (const event &ev)

A free function to convert an event into an informative string, just enough to save some debugging time.

- bool file access (const std::string &targetfile, int mode)
- bool file exists (const std::string &filename)

Checks a file for existence.

bool file_readable (const std::string &filename)

Checks a file for readability.

• bool file_writable (const std::string &filename)

Checks a file for writability.

• bool file_accessible (const std::string &filename)

Checks a file for readability and writability.

bool file executable (const std::string &filename)

Checks a file for the ability to be executed.

• bool file is directory (const std::string &filename)

Checks a file to see if it is a directory.

bool make_directory (const std::string &pathname)

A function to ensure that the \sim /.config/sequencer64 directory exists.

bool ppqn_is_valid (int ppqn)

Common code for handling PPQN settings.

int jack_sync_callback (jack_transport_state_t state, jack_position_t *pos, void *arg)

Global functions for JACK support and JACK sessions.

void jack shutdown callback (void *arg)

This callback is to shut down JACK by clearing the jack_assistant :: m_jack_running flag.

void jack_timebase_callback (jack_transport_state_t state, jack_nframes_t nframes, jack_position_t *pos, int new_pos, void *arg)

The JACK timebase function defined here sets the JACK position structure.

- int jack process callback (jack nframes t nframes, void *arg)
- void jack_session_callback (jack_session_event_t *ev, void *arg)

Set the m_jsession_ev (event) value of the perform object.

std::string keyval name (unsigned int key)

Obtains the name of the key.

void keyval_normalize (keys_perform_transfer &k)

For the case in which the "rc" file is missing or corrupt, this function makes sure that each control key has a reasonable value

bool create lash driver (perform &p, int argc, char **argv)

Creates and starts a lash object.

• lash * lash driver ()

Provides access to the lash object.

void delete_lash_driver ()

Deletes the last object.

void * output_thread_func (void *p)

Global functions defined in perform.cpp.

void * input thread func (void *myperf)

Set up the performance, and set the process to realtime privileges.

rc_settings & rc ()

Returns a reference to the global rc_settings object.

• user settings & usr ()

Returns a reference to the global user_settings object, for better encapsulation.

int choose_ppqn (int ppqn)

Common code for handling PPQN settings.

• long min (long a, long b)

min() for long values.

• static std::string make_section_name (const std::string &label, int value)

Provides a purely internal, ad hoc helper function to create numbered section names for the userfile class.

• font & font render ()

The p_font_renderer pointer was once created in the main module, sequencer64.cpp.

Gtk::Adjustment & adjustment_dummy ()

Provides a way to provide a dummy Gtk::Adjustment object, but not create one until it is actually needed, so that the Glib/Gtk infrastructure is ready for it.

• void update_mainwid_sequences ()

This global function in the seq64 namespace calls mainwid :: update_sequences_on_window(), if the global mainwid object exists.

• void update_perfedit_sequences ()

This global function in the seq64 namespace calls perfedit :: draw_sequences(), if the global perfedit objects exist.

int FF_RW_timeout (void *)

This global function in the seq64 namespace is passed to the gtk_timeout callback.

• static long clamp (long val, long low, long hi)

An internal function used by the FruitySegRollInput class.

• static long clamp (long val, long low, long hi)

An internal function used by the FruitySeqRollInput class.

Variables

std::string c controller names [SEQ64 MIDI COUNT MAX]

Provides the default names of MIDI controllers.

const midibyte EVENT_STATUS_BIT

This highest bit of the status byte is always 1.

const midibyte EVENT_ANY

Channel Voice Messages.

- const midibyte EVENT NOTE OFF
- · const midibyte EVENT NOTE ON
- const midibyte EVENT_AFTERTOUCH

- const midibyte EVENT_CONTROL_CHANGE
- const midibyte EVENT_PROGRAM_CHANGE
- · const midibyte EVENT CHANNEL PRESSURE
- · const midibyte EVENT PITCH WHEEL
- const midibyte EVENT MIDI SYSEX

System Messages.

- const midibyte EVENT_MIDI_QUARTER_FRAME
- · const midibyte EVENT_MIDI_SONG_POS
- const midibyte EVENT MIDI SONG SELECT
- · const midibyte EVENT MIDI SONG F4
- const midibyte EVENT_MIDI_SONG_F5
- const midibyte EVENT_MIDI_TUNE_SELECT
- · const midibyte EVENT MIDI SYSEX END
- const midibyte EVENT MIDI SYSEX CONTINUE
- const midibyte EVENT_MIDI_CLOCK
- const midibyte EVENT MIDI SONG F9
- const midibyte EVENT_MIDI_START
- const midibyte EVENT_MIDI_CONTINUE
- · const midibyte EVENT MIDI STOP
- const midibyte EVENT_MIDI_SONG_FD
- const midibyte EVENT_MIDI_ACTIVE_SENS
- const midibyte EVENT_MIDI_RESET
- const midibyte EVENT_MIDI_META

0xFF is a MIDI "escape code" used in MIDI files to introduce a MIDI meta event.

• const midibyte EVENT_NULL_CHANNEL

This value of 0xFF is Sequencer64's channel value that indicates that the event's m_channel value is bogus.

const midibyte EVENT_GET_CHAN_MASK

These file masks are used to obtain or to mask off the channel data from a status byte.

- const midibyte EVENT_CLEAR_CHAN_MASK
- · const int EVENTS_ALL

Variable from the "stazed" extras.

- const int EVENTS UNSELECTED
- · const int c_midibus_output_size

Manifest global constants.

const int c_midibus_input_size

 $The \ c_midibus_input_size \ value \ is \ passed, \ in \ mastermidibus, \ to \ snd_seq_set_input_buffer_size().$

const int c_midibus_sysex_chunk

Controls the amount a SysEx data sent at one time, in the midibus module.

const midilong c_midibus

Provides tags used by the midifile class to control the reading and writing of the extra "proprietary" information stored in a Seq24 MIDI file.

const midilong c_midich

Track channel number.

const midilong c_midiclocks

Track clocking.

const midilong c_triggers

See c_triggers_new.

const midilong c_notes

Song data.

· const midilong c_timesig

Track time signature.

const midilong c_bpmtag

Song beats/minute.

const midilong c_triggers_new

Track trigger data.

· const midilong c_mutegroups

Song mute group data.

· const midilong c midictrl

Song MIDI control.

const midilong c_musickey

The track's key.

· const midilong c_musicscale

The track's scale.

· const midilong c backsequence

Track background sequence.

· const midilong c_transpose

Track transpose value.

const midilong c_perf_bp_mes

Perfedit beats/measure.

· const midilong c_perf_bw

Perfedit beat-width.

· const int c midi track ctrl

Pseudo control values for associating MIDI events (I think) with automation of some of the controls in seq24.

- · const int c midi control bpm up
- const int c_midi_control_bpm_dn
- · const int c midi control ss up
- · const int c_midi_control_ss_dn
- · const int c_midi_control_mod_replace
- · const int c_midi_control_mod_snapshot
- · const int c midi control mod queue
- const int c_midi_control_mod_gmute
- const int c_midi_control_mod_glearn
- const int c_midi_control_play_ss
- const int c_midi_controls
- const bool c_scales_policy [c_scale_size][SEQ64_OCTAVE_SIZE]

Each value in the kind of scale is denoted by a true value in these arrays.

const int c_scales_transpose_up [c_scale_size][SEQ64_OCTAVE_SIZE]

Increment values needed to transpose each scale up so that it remains in the same key.

const int c_scales_transpose_dn [c_scale_size][SEQ64_OCTAVE_SIZE]

Making these positive makes it easier to read, but the actual array contains negative values.

• const char c_scales_text [c_scale_size][20]

The names of the currently-supported scales.

const char c_key_text [SEQ64_OCTAVE_SIZE][4]

Provides the entries for the Key dropdown menu in the Pattern Editor window.

const char c_interval_text [16][4]

Provides the entries for the Interval dropdown menu in the Pattern Editor window.

• const char c_chord_text [8][6]

Provides the entries for the Chord dropdown menu in the Pattern Editor window.

• const int c_max_instruments

Provides the maximum number of instruments that can be defined in the \sim /. seq24usr or \sim /.config/sequencer64/sequencer6 file.

• const int c_max_busses

Provides the maximum number of MIDI buss definitions supported in the "user" file.

· static const std::string versiontext

Sets up the "hardwired" version text for Sequencer64.

static struct option long_options []

A structure for command parsing that provides the long forms of command-line arguments, and associates them with their respective short form.

static const std::string s_arg_list

Provides a complete list of the short options, and is passed to getopt_long().

static const char *const s_help_1a

Provides help text.

• static const char *const s help 1b

More help text.

static const char *const s_help_2

Still more help text.

static const char *const s_help_3

Still more help text.

static const char *const s_help_4

Still more help text.

static const std::string s_build_highlight_empty

This section of variables provide static information about the options enabled or disabled during the build.

- · static const std::string s build lash support
- · static const std::string s build jack support
- static const std::string s_build_jack_session
- static const std::string s_build_pause_support
- static const std::string s_build_use_event_map
- static const std::string s_build_chord_generator
- static const std::string s build edit highlight
- static const std::string s_build_timesig_tempo
- static const std::string s_build_midi_vector
- static const std::string s build solid grid
- static const std::string s_build_follow_progress
- static const std::string s statistics support
- struct charpair_t s_character_mapping []

The array of mappings of the non-alphabetic characters.

static lash * s_global_lash_driver

The global pointer to the LASH driver instance.

• static const int c_status_replace

Purely internal constants used with the functions that implement MIDI control for the application.

• static const int c_status_snapshot

This value signals the "snapshot" functionality.

• static const int c_status_queue

This value signals the "queue" functionality.

static rc_settings g_rc_settings

Provides the replacement for all of the other "global_xxx" variables.

• static user_settings g_user_settings

Provides the replacement for all of the other settings in the "user" configuration file, plus some of the "constants" in the globals module.

static const long s handlesize

An internal variable for handle size.

· static const int s jitter amount

An internal variable for user-jitter control.

static mainwid * gs mainwid pointer

Holds a pointer to the single instance of mainwnd for the entire application, once it is created.

• const int c_mainwid_x

The width of the main pattern/sequence grid, in pixels.

- const int c mainwid y
- static perfedit * gs_perfedit_pointer_0

Holds a pointer to the first instance of perfedit for the entire application, once it is created.

static perfedit * gs_perfedit_pointer_1

Holds a pointer to the second instance of perfedit for the entire application, once it is created.

static const long s_handlesize

An internal variable for handle size.

11.2.1 Detailed Description

Obsolete Now a permanent option.

0.9.3 delta-tick calculation code. This code doesn't quite work for generating the proper rate of MIDI clocks, and so have disabled that code until we can figure out what it is we're doing wrong. Do not enable it unless you are willing to test it.

Provides a new option to save the Time Signature and Tempo data that may be present in a MIDI file (in the first track) in the sequence object, and write them back to the MIDI file when saved again, in Sequencer64 format. The SeqSpec events that Seq24 and Sequencer64 save for these "events" are not readable by other MIDI applications, such as QTractor. By enabling this macro, other sequencers can read the correct time-signature and tempo values.

#define SEQ64_HANDLE_TIMESIG_AND_TEMPO

11.2.2 Typedef Documentation

- 11.2.2.1 typedef unsigned char seq64::midibyte
- 11.2.2.2 typedef unsigned char seq64::bussbyte
- 11.2.2.3 typedef unsigned short seq64::midishort
- 11.2.2.4 typedef unsigned long seq64::midilong
- 11.2.2.5 typedef long seq64::midipulse

HOWEVER, CURRENTLY, if you make this value unsigned, then perfroll won't show any notes in the sequence bars!!! Also, a number of manipulations of this type currently depend upon it being a signed value.

11.2.3 Enumeration Type Documentation

11.2.3.1 enum seq64::wave_type_t

We still have to clarify these type values, though.

Enumerator

WAVE_NONE
WAVE_SINE
WAVE_TRIANGLE
WAVE_INVERSE_TRIANGLE
WAVE STEP

11.2.3.2 enum seq64::seq_modifier_t

We have to tweak the names to avoid redeclaration errors and to "personalize" the values. We change "GDK" to "SEQ64".

Since we're getting events from, say Gtk-2.4, but using our (matching) values for comparison, use the CAST_EQ UIVALENT() macro to compare them. Note that we might still end up having to a remapping (e.g. if trying to get the code to work with the Qt framework).

Enumerator

SEQ64_NO_MASK

SEQ64_SHIFT_MASK

SEQ64_LOCK_MASK

SEQ64 CONTROL MASK

SEQ64_MOD1_MASK

SEQ64 MOD2 MASK

SEQ64_MOD3_MASK

SEQ64_MOD4_MASK

SEQ64_MOD5_MASK

SEQ64_BUTTON1_MASK

SEQ64_BUTTON2_MASK

SEQ64_BUTTON3_MASK

SEQ64_BUTTON4_MASK

SEQ64_BUTTON5_MASK

SEQ64_SUPER_MASK Bits 13 and 14 are used by XKB, bits 15 to 25 are unused. Bit 29 is used internally.

SEQ64_HYPER_MASK

SEQ64_META_MASK

SEQ64_RELEASE_MASK

SEQ64_MASK_MAX

11.2.3.3 enum seq64::seq_event_type_t

Only the values we need have been grabbed. We have to tweak the names to avoid redeclaration errors and to "personalize" the values. We change "GDK" to "SEQ64", but, for convenience (to hide errors? :-D), we keep the number the same.

Since we're getting events from, say Gtk-2.4, but using our (matching) values for comparison, use the CAST_EQ UIVALENT() macro to compare them. Note that we might still end up having to a remapping (e.g. if trying to get the code to work with the Qt framework).

Enumerator

SEQ64_NOTHING

SEQ64_DELETE

SEQ64 DESTROY

SEQ64_EXPOSE

SEQ64_MOTION_NOTIFY

SEQ64_BUTTON_PRESS

SEQ64_2BUTTON_PRESS SEQ64_3BUTTON_PRESS SEQ64_BUTTON_RELEASE SEQ64_KEY_PRESS SEQ64_KEY_RELEASE SEQ64_SCROLL SEQ64_EVENT_LAST

11.2.3.4 enum seq64::seq_scroll_direction_t

We have to tweak the names to avoid redeclaration errors and to "personalize" the values. We change "SEQ64" to "SEQ64".

Since we're getting events from, say Gtk-2.4, but using our (matching) values for comparison, use the CAST_EQ UIVALENT() macro to compare them. Note that we might still end up having to a remapping (e.g. if trying to get the code to work with the Qt framework).

Enumerator

SEQ64_SCROLL_UP SEQ64_SCROLL_DOWN SEQ64_SCROLL_LEFT SEQ64_SCROLL_RIGHT

11.2.3.5 enum seq64::clock e

This enumeration was also defined in midibus_portmidi.h, but we put it into this common module to avoid duplication.

Enumerator

- e_clock_off Corresponds to the "Off" selection in the MIDI Clock tab. With this setting, the MIDI Clock is disabled for the buss using this setting. Notes will still be sent that buss, of course. Some software synthesizer might require this setting in order to make a sound.
- e_clock_pos Corresponds to the "Pos" selection in the MIDI Clock tab. With this setting, MIDI Clock will be sent to this buss, and, if playback is starting beyond tick 0, then MIDI Song Position and MIDI Continue will also be sent on this buss.
- e_clock_mod Corresponds to the "Mod" selection in the MIDI Clock tab. With this setting, MIDI Clock and MIDI Start will be sent. But clocking won't begin until the Song Position has reached the start modulo (in 1/16th notes) that is specified.

11.2.3.6 enum seq64::interaction_method_t

Moved here from the globals.h module.

Enumerator

- e_seq24_interaction Use the normal mouse interactions.
- e_fruity_interaction The "fruity" mouse interactions.
- e_number_of_interactions Keep this last... a size value.

11.2.3.7 enum seq64::c_music_scales

Scales can be shown in the piano roll as gray bars for reference purposes.

We've added three more scales; there are still a number of them that could be fruitfully added to the list of scales.

It would be good to offload this stuff into a new "scale" class.

Enumerator

- c_scale_off
- c_scale_major
- c_scale_minor
- c_scale_harmonic_minor
- c_scale_melodic_minor
- c_scale_c_whole_tone
- c_scale_blues
- c_scale_major_pentatonic
- c_scale_minor_pentatonic
- c_scale_size

11.2.3.8 enum seq64::draw_type_t

These values are used in the sequence, seqroll, perfroll, and mainwid classes.

Enumerator

```
DRAW_FIN Indicates that drawing is finished.
```

DRAW_NORMAL_LINKED Used for drawing linked notes.

DRAW_NOTE_ON For starting the drawing of a note.

DRAW_NOTE_OFF For finishing the drawing of a note.

11.2.3.9 enum seq64::mouse_action_e

Enumerator

- e_action_select
- e_action_draw
- e_action_grow

11.2.3.10 enum seq64::edit_action_t

These variables represent actions that can be applied to a selection of notes. One idea would be to add a swing-quantize action. We will reserve the value here, for notes only; not yet used or part of the action menu.

Enumerator

- c_select_all_notes
- c_select_all_events
- c_select_inverse_notes
- c_select_inverse_events
- c_quantize_notes
- c_quantize_events
- c_tighten_events
- c_tighten_notes
- c_transpose_notes
- c_reserved
- c_transpose_h
- c_expand_pattern
- c_compress_pattern
- c_select_even_notes
- c_select_odd_notes
- c_swing_notes

11.2.4 Function Documentation

- 11.2.4.1 bool seq64::extract_timing_numbers (const std::string & s, std::string & part_1, std::string & part_2, std::string & part_3, std::string & fraction)
 - · measures : beats : divisions
 - "213:4:920"
 - "0:1:0"
 - · hours : minutes : seconds . fraction
 - "2:04:12.14"
 - "0:1:2"

Warning

This is not the most efficient implementation you'll ever see. At some point we will tighten it up. This function is tested in the seq64-tests project, in the "calculations_unit_test" module.

s Provides the input time string, in measures or time format, to be processed out part out part out part The destination reference for the first part of the time. The destination reference for the second part of the time. Generated by ❷oxygen out part part The destination reference for the third part of the time. 3			_
	s	Provides the input time string, in measures or time format, to be processed.	
Generated by ②poxygen out part← The destination reference for the third part of the time.	part←	The destination reference for the first part of the time.	
Generated by ②poxygen out part← The destination reference for the third part of the time.	_1		
out part The destination reference for the third part of the time.	part⇔	The destination reference for the second part of the time.	1
i i i i i i i i i i i i i i i i i i i	b <u>y</u> ⊉ oxygen		
_3	part⊷	The destination reference for the third part of the time.	
	_3		
out fraction The destination reference for the fractional part of the time.	fraction	The destination reference for the fractional part of the time.	
out		part← _1 part← by £ oxygen part← _3	part The destination reference for the first part of the time. _1 _1 part The destination reference for the second part of the time. by ②boxygen _3 The destination reference for the third part of the time. _3

Returns true if a reasonable portion (3 numbers) was good for extraction. The fraction part will start with a period for easier conversion to fractional seconds.

11.2.4.2 std::string seq64::pulses_to_string (midipulse p)

Todo Still needs to be unit tested.

Parameters

p The MIDI pulse/tick value to be converted.

Returns

Returns the string as an unsigned ASCII integer number.

11.2.4.3 std::string seq64::pulses_to_measurestring (midipulse p, const midi_timing & seqparms)

Parameters

p	The number of MIDI pulses (clocks, divisions, ticks, you name it) to be converted. If the value is SEQ64_ILLEGAL_PULSE, it is converted to 0, because callers don't generally worry about such niceties, and the least we can do is convert illegal measure-strings (like "000:0:000") to a legal value.
seqparms	This small structure provides the beats/measure, beat-width, and PPQN that hold for the sequence involved in this calculation. These values are needed in the calculations

Returns

Returns the string, in measures notation, for the absolute pulses that mark this duration.

11.2.4.4 bool seq64::pulses_to_midi_measures (midipulse p, const midi_timing & seqparms, midi_measures & measures)

$$m = p * W / (4 * P * B)$$

	р	Provides the MIDI pulses (as in "pulses per quarter note") that are to be converted to MIDI measures format.
	seqparms	This small structure provides the beats/measure (B), beat-width (W), and PPQN (P) that hold for the sequence involved in this calculation. The beats/minute (T for tempo) value is not needed.
out	measures	Provides the current MIDI song time structure to hold the results, which are the measures, beats, and divisions values for the time of interest. Note that the measures and beats are corrected to be re 1, not 0.

Returns true if the calculations were able to be made. The P, B, and W values all need to be greater than 0.

11.2.4.5 std::string seq64::pulses_to_timestring (midipulse p, int bpm, int ppqn)

If the fraction part is 0, then it is not shown. Examples:

```
- "0:0:0"

- "0:0:0.102333"

- "12:3:1"

- "12:3:1.000001"
```

Parameters

p	Provides the number of ticks, pulses, or divisions in the MIDI event time.
bpm Provides the tempo of the song, in beats/minute.	
ppqn Provides the pulses-per-quarter-note of the song.	

Returns

Returns the time-string representation of the pulse (ticks) value.

11.2.4.6 std::string seq64::pulses_to_timestring (midipulse p, const midi_timing & timinginfo)

See the other pulses_to_timestring() overload.

Todo Still needs to be unit tested.

Parameters

р	Provides the number of ticks, pulses, or divisions in the MIDI event time.	
timinginfo Provides the tempo of the song, in beats/minute, and the pulse-per-quarter-note of the song		

Returns

Returns the return-value of the other pulses_to_timestring() function.

11.2.4.7 midipulse seq64::measurestring_to_pulses (const std::string & measures, const midi_timing & seqparms)

measures	Provides the current MIDI song time in "measures:beats:divisions" format, where divisions are the MIDI pulses in "pulses-per-quarter-note".
seqparms	This small structure provides the beats/measure, beat-width, and PPQN that hold for the sequence involved in this calculation.

Returns the absolute pulses that mark this duration. If the input string is empty, then 0 is returned.

11.2.4.8 midipulse seq64::midi_measures_to_pulses (const midi_measures & measures, const midi_timing & segparms)

p = 4 * P * m * B / W p == pulse count (ticks or pulses) m == number of measures B == beats per measure (constant) P == pulses per quarter-note (constant) W == beat width in beats per measure (constant)

Note that the 0-pulse MIDI measure is "1:1:0", which means "at the beginning of the first beat of the first measure, no pulses'. It is not "0:0:0" as one might expect.

Parameters

measures	Provides the current MIDI song time structure holding the measures, beats, and divisions values for the time of interest.
seqparms	This small structure provides the beats/measure, beat-width, and PPQN that hold for the sequence involved in this calculation.

Returns

Returns the absolute pulses that mark this duration. If the pulse-value cannot be calculated, then SEQ64_I ← LLEGAL PULSE is returned.

11.2.4.9 midipulse seq64::timestring_to_pulses (const std::string & timestring, int bpm, int ppqn)

Parameters

timestring The time value to be converted, which must be of the form "hh:mm:ss" or "hh:mm	
bpm The beats-per-minute tempo (e.g. 120) of the current MIDI song. ppqn The parts-per-quarter note precision (e.g. 192) of the current MIDI song.	

Returns

Returns 0 if an error occurred or if the number actually translated to 0.

This conversion assumes that the fractional parts of the seconds is padded with zeroes on the left or right to 6 digits.

This conversion assumes that the fractional parts of the seconds is padded with zeroes on the left or right to 6 digits.

11.2.4.10 midipulse seq64::string_to_pulses (const std::string & s, const midi timing & mt)

First, the type of string is deduced by the characters in the string. If the string contains two colons and a decimal point, it is assumed to be a time-string ("hh:mm:ss.frac"); in addition ss will have to be less than 60.

If the string just contains two colons, then it is assumed to be a measure-string ("measures:beats:divisions").

If it has none of the above, it is assumed to be pulses. Testing is not rigorous.

Parameters

s	Provides the string to convert to pulses.	
mt	Provides the structure needed to provide BPM and other values needed for some of the conversions done	1
	by this function.	

Returns

Returns the string as converted to MIDI pulses (or divisions, clocks, ticks, whatever you call it).

11.2.4.11 midibyte seq64::string_to_midibyte (const std::string & s)

This function bypasses characters until it finds a digit (whether part of the number or a "0x" construct), and then converts it.

Parameters

s Provides the string to convert to a MIDI byte.

Returns

Returns the MIDI byte value represented by the string.

11.2.4.12 std::string seq64::shorten_file_spec (const std::string & fpath, int leng)

This is done by removing character in the middle, if necessary, and replacing them with an ellipse.

This function operates by first trying to find the <code>/home directory</code>. If found, it strips off <code>/home/username and replace</code> it with the Linux \sim replacement for the <code>\$HOME</code> environment variable. This function assumes that the "username" portion *must* exist, and that there's no goofy stuff like double-slashes in the path.

Parameters

fpath	The file specification, including the full path to the file, and the name of the file	
leng	leng Provides the length to which to limit the string.	

Returns

Returns the fpath parameter, possibly shortened to fit within the desired length.

11.2.4.13 bool seq64::string_not_void (const std::string & s)

Provides essentially the opposite test that string_is_void() provides. The definition of white-space is provided by the std::isspace() function/macro.

Parameters

s The string pointer to check for emptiness.

Returns

Returns true if the pointer is valid, the string has a non-zero length, and is not just white-space.

11.2.4.14 bool seq64::string_is_void (const std::string & s)

Meant to have essentially the opposite result of string_not_void(). The meaning of empty is special here, as it refers to a string being useless as a token:

- The string is of zero length.
- The string has only white-space characters in it, where the isspace() macro provides the definition of white-space.

Parameters

s The string pointer to check for emptiness.

Returns

Returns true if the string has a zero length, or is only white-space.

11.2.4.15 bool seq64::strings_match (const std::string & target, const std::string & x)

The strings_match() function returns true if the comparison items are identical, without case-sensitivity in character content up to the length of the secondary string. This allows abbreviations to match. (And, in scanning routines, the first match is immediately accepted.)

Parameters

target	The primary string in the comparison. This is the target string, the one we hope to match. It is assumed to be non-empty, and the result is false if it is empty.	
Х	The secondary string in the comparison. It must be no longer than the target string, or the match is false.	

Returns

Returns true if both strings are are identical in characters, up to the length of the secondary string, with the case of the characters being insignificant. Otherwise, false is returned.

11.2.4.16 int seq64::log2_time_sig_value (int tsd)

Useful in converting a time signature's denominator to a Time Signature meta event's "dd" value.

Parameters

tsd The time signature denominator, which must be a power of 2: 2, 4, 8, 16, or 32.

Returns

Returns the power of 2 that achieves the *tsd* parameter value.

11.2.4.17 void seq64::tempo_us_to_bytes (midibyte t[3], int tempo_us)

Recall the format of a Tempo event:

0 FF 51 03 t2 t1 t0 (tempo as number of microseconds per quarter note)

This code is the inverse of the lines of code around line 768 in midifile.cpp, which is basically ((t2 * 256) + t1) * 256 + t0 .

As a test case, note that the default tempo is 120 beats/minute, which is equivalent to ttttt=500000 (0x07A120).

Parameters

t	Provides a small array of 3 elements to hold each tempo byt	
tempo_us	Provides the temp value in microseconds per quarter note.	

11.2.4.18 int seq64::zoom_power_of_2 (int ppqn)

The default starting zoom is 2, but this value is suitable only for PPQN of 192 and below. Also, zoom currently works consistently only if it is a power of 2. For starters, we scale the zoom to the selected ppqn, and then shift it each way to get a suitable power of two.

Parameters

ppq	n T	he ppqn	of interest.

Returns

Returns the power of 2 appropriate for the given PPQN value.

11.2.4.19 double seq64::beats_per_minute_from_tempo_us (double tempous) [inline]

The tempo event's numeric value is given in 3 bytes, and is in units of microseconds-per-quarter-note (us/qn).

	tempo	The value of the Tempo meta-event, in units of us/qn. If this value is 0, we'll get an arithmetic exception.
--	-------	--

Returns the beats per minute. If the tempo value is too small, then this function will crash. :-D

11.2.4.20 double seq64::tempo_us_from_beats_per_minute(double bpm) [inline]

Parameters

bpn	The value of beats-per-minute	. If this value is 0, we'll get an arithmetic exception.
-----	-------------------------------	--

Returns

Returns the tempo in qn/us. If the bpm value is too small, then this function will crash. :-D

11.2.4.21 long seq64::tempo_to_us(int bpm) [inline]

120 beats/minute) to microseconds.

Parameters

bpm	Provides the tempo in beats/minute.
-----	-------------------------------------

11.2.4.22 double seq64::pulse_length_us (int bpm, int ppqn) [inline]

The formula for the pulse-length in seconds is:

Parameters

bpm	Provides the beats-per-minute value. No sanity check is made. If this value is 0, we'll get an arithmetic exception.
ppqn	Provides the pulses-per-quarter-note value. No sanity check is made. If this value is 0, we'll get an arithmetic exception.

Returns

Returns the pulse length in microseconds. If either parameter is invalid, then this function will crash. :-D

11.2.4.23 double seq64::delta time us to ticks (unsigned long us, int bpm, int ppqn) [inline]

This function is the inverse of ticks_to_delta_time_us().

Please note that terms "ticks" and "pulses" are equivalent, and refer to the "pulses" in "pulses per quarter note".

Note that this formula assumes that a beat is a quarter note. If a beat is an eighth note, then the P value would be halved, because there would be only 96 pulses per beat. We will implement an additional function to account for the beat; the current function merely blesses some calculations made in the application.

Parameters

us	The number of microseconds in the delta time.
bpm	Provides the beats-per-minute value, otherwise known as the "tempo".
ppqn	Provides the pulses-per-quarter-note value, otherwise known as the "division".

Returns

Returns the tick value.

11.2.4.24 double seq64::ticks_to_delta_time_us (midipulse delta_ticks, int bpm, int ppqn) [inline]

The inverse of delta_time_us_to_ticks().

Please note that terms "ticks" and "pulses" are equivalent, and refer to the "pulses" in "pulses per quarter note".

Old: 60000000.0 * double(delta_ticks) / (double(bpm) * double(ppqn));

Parameters

delta_ticks	The number of ticks or "clocks".
bpm	Provides the beats-per-minute value, otherwise known as the "tempo".
ppqn	Provides the pulses-per-quarter-note value, otherwise known as the "division".

Returns

Returns the time value in microseconds.

11.2.4.25 double seq64::clock_tick_duration_bogus (int bpm, int ppqn) [inline]

Deprecated This is a somewhat bogus calculation used only for "statistical" output in the old perform module. Name changed to reflect this unfortunate fact. Use pulse_length_us() instead.

MIDI_CLOCK_IN_PPQN is 24.

bpm	Provides the beats-per-minute value. No sanity check is made. If this value is 0, we'll get an arithme exception.	
ppqn	Provides the pulses-per-quarter-note value. No sanity check is made. If this value is 0, we'll get an arithmetic exception.	

Returns

Returns the clock tick duration in microseconds. If either parameter is invalid, this will crash. Who wants to waste time on value checks here? :-D

11.2.4.26 int seq64::clock_ticks_from_ppqn (int ppqn) [inline]

Parameters

ppqn	The number of pulses per quarter note. For example, the default value for Seq24 is 192.
------	---

Returns

The integer value of ppqn / 24 [MIDI_CLOCK_IN_PPQN] is returned.

11.2.4.27 double seq64::double_ticks_from_ppqn (int ppqn) [inline]

The same as clock_ticks_from_ppqn(), but returned as a double float.

Parameters

ppqn	The number of pulses per quarter note.
------	--

Returns

The double value of ppqn / 24 [SEQ64_MIDI_CLOCK_IN_PPQN]_is returned.

11.2.4.28 midipulse seq64::pulses_per_measure(int ppqn = SEQ64_DEFAULT_PPQN) [inline]

This calculation is extremely simple, and it provides an important constraint to pulse (ticks) calculations: the number of pulses in a measure is always 4 times the PPQN value, regardless of the time signature. The number pulses in a 7/8 measure is the the same as in a 4/4/ measure.

11.2.4.29 midipulse seq64::measures_to_ticks (int bpm, int ppqn, int bw, int measures = 1) [inline]

This function is called in seqedit::apply_length(), when the user selects a sequence length in measures. That function calculates the length in ticks. The number of pulses is given by the number of quarter notes times the pulses per quarter note. The number of quarter notes is given by the measures times the quarter notes per measure. The quarter notes per measure is given by the beats per measure times 4 divided by beat_width beats. So:

```
p = 4 * P * m * B / W
    p == pulse count (ticks or pulses)
    m == number of measures
    B == beats per measure (constant)
    P == pulses per quarter-note (constant)
    W == beat width in beats per measure (constant)

For our "b4uacuse" MIDI file, M can be about 100 measures, B is 4,
P can be 192 (but we want to support higher values), and W is 4.
So p = 100 * 4 * 4 * 192 / 4 = 76800 ticks.

Note that 4 * P is a constraint encapsulated by the inline function pulses_per_measure().
```

bpm	The B value in the equation, beats/measure.
ppqn	The P value in the equation, pulses/qn.
bw	The W value in the equation, the denominator of the time signature. If this value is 0, we'll get an arithmetic exception (crash), so we just return 0 in this case.
measures	The M value in the equation. It defaults to 1, in case one desires a simple "ticks per measure" number.

Returns

Returns the L value (ticks or pulses) as calculated via the given equation. If bw is 0, then 0 is returned.

```
11.2.4.30 double seq64::wave_func ( double angle, wave_type_t wavetype )
```

We extracted this function from mattias's Ifownd module, as it is more generally useful.

Parameters

angle Provides the radial angle to be applied.	
wavetype Provides the wave_type_t value to select the type of wave data-poin	Provides the wave_type_t value to select the type of wave data-point to be generated.

```
11.2.4.31 bool seq64::help_check (int argc, char * argv[])
```

Also check for the –legacy option. Finally, it also checks for the "?" option that people sometimes use as a guess to get help.

Parameters

argc	The number of command-line arguments.
argv	The array of command-line argument pointers.

Returns

Returns true only if -V, -version, -h, -help, or "?" were encountered. If the legacy options occurred, then rc().legacy format(true) is called, as a side effect, because it will be needed before we parse the options.

```
11.2.4.32 bool seq64::parse_options_files ( perform & p, int argc, char * argv[] )
```

It probably requires this call preceding: Gtk::Main kit(argc, argv), to strip any GTK+-specific parameters the knowledgeable user may have added. Usage:

```
Gtk::Main kit(argc, argv);
seq64::gui_assistant_gtk2 gui;
seq64::perform p(gui);
```

It also requires the caller to call rc().set_defaults() and usr().set_defaults(). The caller can then use the command-line to make any modifications to the setting that will be used here. The biggest example is the -r/-reveal-alsa-ports option, which determines if the MIDI buss definition strings are read from the 'user' configuration file.

Instead of the legacy Seq24 names, we use the new configuration file-names, located in the \sim /.config/sequencer64 directory. However, if they are not found, we no longer fall back to the legacy configuration file-names. If the – legacy option is in force, use only the legacy configuration file-name. The code also ensures the directory exists. CURRENTLY LINUX-SPECIFIC. See the rc_settings class for how this works.

```
std::string cfg_dir = seq64::rc().home_config_directory();
if (cfg_dir.empty())
    return EXIT_FAILURE;
```

Change Note ca 2016-04-03 We were parsing the user-file first, but we now need to parse the rc-file first, to get the manual-alsa-ports option, so that we can avoid overriding the port names that the ALSA system provides, if the manual-alsa-option is false.

Parameters

p	Provides the perform object that will be affected by the new parameters.	
argc	The number of command-line arguments.	
argv	The array of command-line argument pointers.	

Returns

Returns true if the reading of both configuration files succeeded.

```
11.2.4.33 int seq64::parse_command_line_options ( int argc, char * argv[] )
```

Note that, since we call this function twice (once before the configuration files are parsed, and once after), we have to make sure that the global value optind is reset to 0 before calling this function. Note that the traditional reset value for optind is 1, but 0 is used in GNU code to trigger the internal initialization routine of get opt().

Parameters

argc	The number of command-line arguments.
argv	The array of command-line argument pointers.

Returns

Returns the value of optind if no help-related options were provided.

11.2.4.34 bool seq64::write_options_files (const perform & p)

This function gets any legacy global variables, on the theory that they might have been changed.

Parameters

p Provides the perform object that may provide new values for the parameters.

Returns

Returns true if both files were saved successfully. Otherwise returns false. But even if one write failed, the other might have succeeded.

11.2.4.35 std::string seq64::build_details ()

Returns

Returns an ordered, human-readable string enumerating the built-in features of this application.

11.2.4.36 std::string seq64::to_string (const event & ev)

Nothing fancy. If you want that, use the midicvt project.

Parameters

ev The event to put on show.

Returns

Returns the string representation of the event parameter.

11.2.4.37 bool seq64::file_access (const std::string & targetfile, int mode)

11.2.4.38 bool seq64::file_exists (const std::string & filename)

Parameters

filename Provides the name of the file to be checked.

Returns

Returns 'true' if the file exists.

11.2.4.39 bool seq64::file_readable (const std::string & filename)

filename	Provides the name of the file to be checked.	
----------	--	--

Returns

Returns 'true' if the file is readable.

11.2.4.40 bool seq64::file_writable (const std::string & filename)

Parameters

filename	Provides the name of the file to be checked.
----------	--

Returns

Returns 'true' if the file is writable.

11.2.4.41 bool seq64::file_accessible (const std::string & filename)

An even stronger test than file_exists. At present, we see no need to distinguish read and write permissions. We assume the file is accessible only if the file has both permissions.

Parameters

of the file to be checked.

Returns

Returns 'true' if the file is readable and writable.

11.2.4.42 bool seq64::file_executable (const std::string & filename)

Parameters

filename Provides the name of the file to be checked.

Returns

Returns 'true' if the file exists.

11.2.4.43 bool seq64::file_is_directory (const std::string & filename)

This function is also used in the function of the same name in fileutilities.cpp.

Provides the name of the directory to be checked.

Returns

Returns 'true' if the file is a directory.

11.2.4.44 bool seq64::make_directory (const std::string & pathname)

This function is actually a little more general than that, but it is not sufficiently general, in general.

Parameters

Returns

Returns true if the path-name exists.

11.2.4.45 bool seq64::ppqn_is_valid (int ppqn) [inline]

Validates a PPQN value.

Parameters

ppqn	Provides the PPQN value to be used.

Returns

Returns true if the ppqn parameter is between MINIMUM_PPQN and MAXIMUM_PPQN, or is set to SE

Q64_USE_DEFAULT_PPQN (-1).

11.2.4.46 int seq64::jack_sync_callback (jack_transport_state_t state, jack_position_t * pos, void * arg)

This JACK synchronization callback informs the specified perform object of the current state and parameters of JACK.

The transport state will be:

- JackTransportStopped when a new position is requested.
- JackTransportStarting when the transport is waiting to start.
- JackTransportRolling when the timeout has expired, and the position is now a moving target.

This is the slow-sync callback, which stazed replaces with jack_process_callback().

state	The JACK Transport state.
pos	The JACK position value.
arg	The pointer to the jack_assistant object. Currently not checked for nullity, nor dynamic-casted.

Returns

Returns 1 if the function works, and 0 if something was wrong.

11.2.4.47 void seq64::jack_shutdown_callback (void * arg)

Parameters

arg Points to the jack_assistant in charge of JACK support for the perform object.

11.2.4.48 void seq64::jack_timebase_callback (jack_transport_state_t state, jack_nframes_t nframes, jack_position_t * pos, int new_pos, void * arg)

The original version of the function worked properly with Hydrogen, but not with Klick. The new code seems to work with both. More testing and clarification is needed. This new code was "discovered" in the source-code for the "SooperLooper" project:

http://essej.net/sooperlooper/

The first difference with the new code is that it handles the case where the JACK position is moved (new_pos == true). If this is true, and the JackPositionBBT bit is off in pos->valid, then the new BBT value is set.

The seconds set of differences are in the "else" clause. In the new code, it is very simple: calculate the new tick value, back it off by the number of ticks in a beat, and perhaps go to the first beat of the next bar.

In the old code (complex!), the simple BBT adjustment is always made. This changes (perhaps) the beats_per_bar, beat_type, etc. We need to make these settings use the actual global values for beats set for Sequencer64. Then, if transitioning from JackTransportStarting to JackTransportRolling (instead of checking new_pos!), the BBT values (bar, beat, and tick) are finally adjusted. Here are the steps, with old and new steps noted:

- -# Calculate the "delta" ticks based on the current frame, the ticks_per_beat, the beats_per_minute, and the frame_rate. The old code saves this in a local, the new code assigns it to pos->tick.
- -# Old code: save this delta as a positive value.
- -# Figure out the settings and modify bar, beat, tick, and bar_start_tick. The old and new code seem to have the same intent, but it seems like the new code is faster and also correct.
 - Old code: Calculations are made by division and mod operations.
 - New code: Calculations are made by increments and decrements in a while loop.

Stazed:

The call to jack_timebase_callback() to supply JACK with BBT, etc. would occasionally fail when the pos information had zero or some garbage in the pos.frame_rate variable. This would occur when there was a rapid change of frame position by another client... i.e. qjackctl. From the JACK API:

pos address of the position structure for the next cycle; pos->frame will be its frame number. If new_pos is FALSE, this structure contains extended position information from the current cycle. If TRUE, it contains whatever was set by the requester. The timebase_callback's task is to update the extended information here."

The "If TRUE" line seems to be the issue. It seems that qjackctl does not always set pos.frame_rate so we get garbage and some strange BBT calculations that display in qjackctl. So we need to set it here and just use m_jack_frame_rate for calculations instead of pos.frame_rate.

Parameters

state	Indicates the current state of JACK transport.
nframes	The number of JACK frames in the current time period.
pos	Provides the position structure to be filled in, the address of the position structure for the next cycle; pos->frame will be its frame number. If new_pos is FALSE, this structure contains extended position information from the current cycle. If TRUE, it contains whatever was set by the requester. The timebase_callback's task is to update the extended information here.
new_pos	TRUE (non-zero) for a newly requested pos, or for the first cycle after the timebase_callback is defined. This is usually 0 in Sequencer64 at present, and 1 if one, say, presses "rewind" in qjackctl.
arg	Provides the jack_assistant pointer, currently unchecked for nullity.

11.2.4.49 int seq64::jack_process_callback (jack_nframes_t nframes, void * arg)

11.2.4.50 void seq64::jack_session_callback (jack_session_event_t * ev, void * arg)

Glib is then used to connect in perform::jack_session_event(). However, the perform object's GUI-support interface is used instead of the following, so that the libseq64 library can be independent of a specific GUI framework:

```
Glib::signal_idle().
    connect(sigc::mem_fun(*jack, &jack_assistant::session_event));
```

Parameters

ev	The JACK event to be set.
arg	The pointer to the jack_assistant object. Currently not checked for nullity.

11.2.4.51 std::string seq64::keyval_name (unsigned int key)

In gtkmm, this is done via the gdk_keyval_name() function. Here, in the base class, we just provide an easy-to-create string. Note that this is a free function, not a class member.

key	Provides the key-number to be converted to a key name.
-----	--

Returns

Returns the key name as looked up by the GDK infrastructure. If the key is not found, then an empty string is returned.

11.2.4.52 void seq64::keyval_normalize (keys_perform_transfer & k)

Otherwise, random values, unchecked, can cause the application to crash.

Any field that is 0 or greater than 65536 is fixed. Not perfect, but better than allowing random values to be used.

Parameters

11.2.4.53 bool seq64::create_lash_driver (perform & p, int argc, char ** argv)

Initializes the lash driver (strips lash-specific command line arguments), then connects to the LASH daemon and polls events.

This function will always be called from the main routine, and called only once. Note that we don't need that darn SEQ64_LASH_SUPPORT macro in client code anymore.

Parameters

р	The perform object that needs to implement LASH support.
argc	The number of command-line arguments.
argv	The command-line arguments.

Returns

This function returns true if a lash object was created. This function will not create one if not configured to, if the command-line options did not specify the creation of the LASH driver, or if the LASH driver was already created.

Returns

Returns the pointer to the LASH driver if it exists. Otherwise a null pointer is returned. The caller *must always check* the return value.

```
11.2.4.55 void seq64::delete_lash_driver()
```

This function will always be called from the main routine, once. The other lash-pointer functions will know if the pointer has been deleted.

```
11.2.4.56 void * seq64::output_thread_func ( void * myperf )
```

Set up the performance, set the process to realtime privileges, and then start the output function.

Parameters

myperf	Provides the perform object instance that is to be used. Its output_func() is called. Currently, this
	parameter is not validated, for speed.

Returns

Always returns nullptr.

```
11.2.4.57 void * seq64::input_thread_func ( void * myperf )
```

Parameters

myperf	Provides the perform object instance that is to be used. Its output_func() is called. Currently, this
	parameter is not validated, for speed.

Returns

Always returns nullptr.

```
11.2.4.58 rc_settings & seq64::rc()
```

Why a function instead of direct variable access? Encapsulation. We are then free to change the way "global" settings are accessed, without changing client code.

Returns

Returns the global object g_rc_settings.

```
11.2.4.59 user_settings & seq64::usr()
```

Returns

Returns the global object g_user_settings.

```
11.2.4.60 int seq64::choose_ppqn ( int ppqn )
```

Putting it here means we can reduce the reliance on the global ppqn.

	ppqn	Provides the PPQN value to be used.	1
--	------	-------------------------------------	---

Returns

Returns the ppqn parameter, unless that parameter is SEQ64_USE_DEFAULT_PPQN (-1), then usr().midi ← _ ppqn is returned.

11.2.4.61 long seq64::min (long a, long b) [inline]

Parameters

а	First operand.
b	Second operand.

Returns

Returns the minimum value of a and b.

11.2.4.62 static std::string seq64::make_section_name (const std::string & label, int value) [static]

Parameters

label	The base-name of the section.
value	The numeric value to append to the section name.

Returns

Returns a string of the form "[basename-1]".

11.2.4.63 font& seq64::font_render() [inline]

We've going to render this pointer obsolete, though, and use a smart factory function to ensure the existence of this pointer, and return a reference to the font object.

We wanted to make the font a const object, but mainwid::on_realize() calls the font::init() function with its window object, and using const is impractical. We don't want to force every caller to deal with the overhead of passing even a null window pointer, either.

However, at some point we need some quarantee that the init() function is called before rendering a string. Right now, we guarantee it only by build order.

Returns

Returns a reference to the object pointed to by sp_font_renderer.

```
11.2.4.64 Gtk::Adjustment & seq64::adjustment_dummy ( )
```

This static object is used so we have an Adjustment to assign to the Adjustment members for classes that don't use them. Clumsy? We shall see.

Anyway, the parameters for this constructor are value, lower, upper, step-increment, and two more values.

```
11.2.4.65 void seq64::update_mainwid_sequences ( )
```

It is used by other objects that can modify the currently-edited sequence shown in the mainwid (main window).

```
11.2.4.66 void seq64::update_perfedit_sequences ( )
```

It is used by other objects (sequence shown in the perfedit (song window).

```
11.2.4.67 int seq64::FF_RW_timeout ( void * arg )
```

```
11.2.4.68 static long seq64::clamp ( long val, long low, long hi ) [inline], [static]
```

11.2.4.69 static long seq64::clamp (long val, long low, long hi) [inline], [static]

11.2.5 Variable Documentation

11.2.5.1 std::string seq64::c_controller_names

This array is used only by the seqedit class.

11.2.5.2 const midibyte seq64::EVENT_STATUS_BIT

11.2.5.3 const midibyte seq64::EVENT_ANY

The following MIDI events are channel messages. The comments represent the one or two data-bytes of the message.

Note that Channel Mode Messages use the same code as the Control Change, but uses reserved controller numbers ranging from 122 to 127.

The EVENT_ANY (0x00) value may prove to be useful in allowing any event to be dealt with. Not sure yet, but the cost is minimal.

- 11.2.5.4 const midibyte seq64::EVENT_NOTE_OFF
- 11.2.5.5 const midibyte seq64::EVENT_NOTE_ON
- 11.2.5.6 const midibyte seq64::EVENT_AFTERTOUCH
- 11.2.5.7 const midibyte seg64::EVENT_CONTROL_CHANGE
- 11.2.5.8 const midibyte seg64::EVENT_PROGRAM_CHANGE
- 11.2.5.9 const midibyte seq64::EVENT_CHANNEL_PRESSURE
- 11.2.5.10 const midibyte seq64::EVENT_PITCH_WHEEL
- 11.2.5.11 const midibyte seq64::EVENT_MIDI_SYSEX

The following MIDI events have no channel. We have included redundant constant variables for the SysEx Start and End bytes just to make it clear that they are part of this sequence of values, though usually treated separately.

Only the following constants are followed by some data bytes:

```
- EVENT_MIDI_SYSEX = 0xF0
- EVENT_MIDI_QUARTER_FRAME = 0xF1 // undefined?
- EVENT_MIDI_SONG_POS = 0xF2
- EVENT_MIDI_SONG_SELECT = 0xF3
```

A MIDI System Exclusive (SYSEX) message starts with F0, followed by the manufacturer ID (how many? bytes), a number of data bytes, and ended by an F7.

- 11.2.5.12 const midibyte seq64::EVENT_MIDI_QUARTER_FRAME
- 11.2.5.13 const midibyte seq64::EVENT_MIDI_SONG_POS
- 11.2.5.14 const midibyte seq64::EVENT_MIDI_SONG_SELECT
- 11.2.5.15 const midibyte seq64::EVENT_MIDI_SONG_F4
- 11.2.5.16 const midibyte seq64::EVENT_MIDI_SONG_F5
- 11.2.5.17 const midibyte seq64::EVENT_MIDI_TUNE_SELECT
- 11.2.5.18 const midibyte seg64::EVENT MIDI SYSEX END
- 11.2.5.19 const midibyte seq64::EVENT_MIDI_SYSEX_CONTINUE
- 11.2.5.20 const midibyte seq64::EVENT_MIDI_CLOCK

11.2.5.21	const midibyte seq64::EVENT_MIDI_SONG_F9
11.2.5.22	const midibyte seq64::EVENT_MIDI_START
11.2.5.23	const midibyte seq64::EVENT_MIDI_CONTINUE
11.2.5.24	const midibyte seq64::EVENT_MIDI_STOP
11.2.5.25	const midibyte seq64::EVENT_MIDI_SONG_FD
11.2.5.26	const midibyte seq64::EVENT_MIDI_ACTIVE_SENS
11.2.5.27	const midibyte seq64::EVENT_MIDI_RESET
11.2.5.28	const midibyte seq64::EVENT_MIDI_META

However, it also means that the channel is encoded in the m_status byte itself. This is our work around to be able to hold a multi-channel SMF 0 track in a sequence. In a Sequencer64 SMF 0 track, every event has a channel. In a Sequencer64 SMF 1 track, the events do not have a channel. Instead, the channel is a global value of the sequence, and is stuffed into each event when the event is played or is written to a MIDI file.

11.2.5.30 const midibyte seq64::EVENT_GET_CHAN_MASK

11.2.5.29 const midibyte seq64::EVENT_NULL_CHANNEL

- 11.2.5.31 const midibyte seq64::EVENT_CLEAR_CHAN_MASK
- 11.2.5.32 const int seq64::EVENTS_ALL

We reversed the parts of each token for consistency with the macros defined above.

- 11.2.5.33 const int seq64::EVENTS_UNSELECTED
- 11.2.5.34 const int seq64::c_midibus_output_size

These constants were also defined in midibus_portmidi.h, but we made them common to both implementations here.

The c_midibus_output_size value is passed, in mastermidibus, to snd_seq_set_output_buffer_size(). Not sure if the value needs to be so large.

11.2.5.35 const int seq64::c_midibus_input_size

Not sure if the value needs to be so large.

11.2.5.36 const int seq64::c_midibus_sysex_chunk

11.2.5.37 const midilong seq64::c_midibus

Some of the information is stored with each track (and in the midi_container-derived classes), and some is stored in the proprietary header.

Track (sequencer-specific) data:

```
c_midibus
c_midich
c_timesig
c_triggers (deprecated)
c_triggers_new
c_musickey (can be in footer, as well)
c_musicscale (ditto)
c_backsequence (ditto)
c_transpose
```

Footer ("proprietary") data:

```
c_midictrl
c_midiclocks
c_notes
c_bpmtag (beats per minute)
c_mutegroups
c_perf_bp_mes (perfedit's beats-per-measure setting)
c_perf_bw (perfedit's beat-width setting)
```

Also see the PDF file in the following project for more information about the "proprietary" data:

 $\verb|https://github.com/ahlstromcj/sequencer64-doc.git|\\$

Note that the track data is read from the MIDI file, but not written directly to the MIDI file. Instead, it is stored in the MIDI container as sequences are edited to used these "sequencer-specific" features. Also note that c_triggers has been replaced by c_triggers_new as the code that marks the triggers stored with a sequence.

As an extension, we can also grab the key, scale, and background sequence value selected in a sequence and write these values as track data, where they can be read in and applied to a specific sequence, when the sequence object is created. These values would not be stored in the legacy format.

Something like this could be done in the "user" configuration file, but then the key and scale would apply to all songs. We don't want that.

We could also add snap and note-length to the per-song defaults, but the "user" configuration file seems like a better place to store these preferences.

Note

The new value c_transpose value is from Stazed's seq32 project. The code to support this option is turned on via the build-configurable SEQ64_STAZED_TRANSPOSE macro, but here we reserved the value even if that option is not enabled by the user. There are additional values from Stazed/seq32, not yet used.Track buss number.

11.2.5.38	const midilong seq64::c_midich
11.2.5.39	const midilong seq64::c_midiclocks
11.2.5.40	const midilong seq64::c_triggers
11.2.5.41	const midilong seq64::c_notes
11.2.5.42	const midilong seq64::c_timesig
11.2.5.43	const midilong seq64::c_bpmtag
11.2.5.44	const midilong seq64::c_triggers_new
11.2.5.45	const midilong seq64::c_mutegroups
11.2.5.46	const midilong seq64::c_midictrl
11.2.5.47	const midilong seq64::c_musickey
11.2.5.48	const midilong seq64::c_musicscale
11.2.5.49	const midilong seq64::c_backsequence
11.2.5.50	const midilong seq64::c_transpose
11.2.5.51	const midilong seq64::c_perf_bp_mes
11.2.5.52	const midilong seq64::c_perf_bw
11.2.5.53	const int seq64::c_midi_track_ctrl

I think the reason for that value is to perhaps handle two sets or something like that. Will figure it out later.

The controls are read in from the "rc" configuration files, and are written to the $c_{midictrl}$ section of the "proprietary" final track in a Seq24/Sequencer64 MIDI file.

The lowest value is $c_{seqs_in_set} * 2 = 64$.

```
11.2.5.54 const int seq64::c_midi_control_bpm_up

11.2.5.55 const int seq64::c_midi_control_bpm_dn

11.2.5.56 const int seq64::c_midi_control_ss_up

11.2.5.57 const int seq64::c_midi_control_ss_dn

11.2.5.58 const int seq64::c_midi_control_mod_replace

11.2.5.59 const int seq64::c_midi_control_mod_snapshot

11.2.5.60 const int seq64::c_midi_control_mod_queue

11.2.5.61 const int seq64::c_midi_control_mod_gmute

11.2.5.62 const int seq64::c_midi_control_mod_glearn

11.2.5.63 const int seq64::c_midi_control_play_ss

11.2.5.64 const int seq64::c_midi_controls

11.2.5.65 const bool seq64::c_scales_policy[c_scale_size][SEQ64_OCTAVE_SIZE]
```

See the following sites for more information:

```
- http://method-behind-the-music.com/theory/scalesandkeys/
- https://en.wikipedia.org/wiki/Heptatonic_scale
```

https://en.wikibooks.org/wiki/Music_Theory/Scales_and_Intervals

Note that melodic minor descends in the same way as the natural minor scale, so it descends differently than it ascends. We don't deal with that trick, at all. In the following table, the scales all start with C, but seq24/sequencer64 allow other starting notes (e.g. "keys").

```
C C# D D# E F F# G G# A A# B
Chromatic
                                                       Notes, chord
Major
                     . D
                            . E F
                                    . G
Minor
                   C . D Eb . F
                                       G Ab . Bb .
                            Eb .
                                          Ab . . B . B
Harmonic Minor C . D Eb .

Melodic Minor C . D Eb .

C Whole Tone C . D . E
Harmonic Minor
                  С
                         D
                                  F
                                        G
                                                       Descending diff.
                                  F
                                       G
                                    F# .
                            . E
                                           G# . A# .
                  C . D
C Whole Tone
                                                       C+7 chord
                   С
                            Eb .
                                  F
                                     Gb G
Blues
                      .
                                           .
                      . D
Major Pentatonic
                  С
                            . E
                                     . G
Minor Pentatonic {\tt C} .
                            Eb . F
                                      G .
                                                Bb .
Octatonic 1
                   С
                      . D Eb .
                                 F Gb . Ab A
                                                       Unimplemented
                                                . B
                  C Db . Eb E F F# G
Octatonic 2
                                                       Unimplemented
                                          . A Bb .
```

11.2.5.66 const int seq64::c_scales_transpose_up[c_scale_size][SEQ64_OCTAVE_SIZE]

For example, if we simply add 1 semitone to each note, it remains a minor key, but it is in a different minor key. Using the transpositions in these arrays, the minor key remains the same minor key.

Major Transpose up Result up	C 2 D	0	D 2 E	0	E 1 F	F 2 G	0	G 2 A	0	A 2 B	0	B 1 C
Minor Transpose up Result up	C 2 D	0	D 1 D#	D# 2 F	0	F 2 G	0	G 1 G#	G# 2 A#	0	A# 2 C	0
Harmonic minor Transpose up Result up	C 2 D		D 1 Eb	Eb 2 F		F 2 G		G 1 Ab	Ab 3 B			B 1 C
Melodic minor Transpose up Result up	C 2 D		D 1 Eb	Eb 2 F		F 2 G		G 2 A		A 2 B		B 1 C
C Whole Tone Transpose up Result up	C 2 D		D 2 E		E 2 F#		2		G# 2 A#		A# 2 C	
Blues Transpose up Result up	C 3 Eb			Eb 2 F		F 1 Gb	Gb 1 G	G 3 Bb			Bb 2 C	
Major Pentatonic Transpose up Result up	C 2 D		D 2 E		E 3 G			G 2 A		A 3 C		
Minor Pentatonic Transpose up Result up	C 3 Eb			Eb 2 F		F 2 G		G 3 Bb			Bb 2 C	

11.2.5.67 const int seq64::c_scales_transpose_dn[c_scale_size][SEQ64_OCTAVE_SIZE]

Major Transpose down	C 1	•	D 2		E 2	F 1		G 2		A 2		B 2
Result down	В	•	C	•	D	E		F		G	•	A
Minor Transpose down	C 2	•	D 2	D# 1	•	F 2		G 2	G# 1		A# 2	
Result down	A#		C	D		D#		F	G		G#	
Harmonic minor	С		D	Eb		F		G	Ab			В
Transpose down Result down	1 B	•	2 C	1 D	•	2 Eb		2 F	1 G	•		3 Ab
Melodic minor	С		D	Eb		F		G		A		В
Transpose down Result down	1 B	:	2 C	1 D		2 Eb		2 F		2 G	•	2 A
C whole tone	С		D		Ε		F#		G#		A#	
C whole tone Transpose down	C 2		D 2		E 2		F#		G# 2		A# 2	
Transpose down	2		2		2		2		2		2	
Transpose down Result down	2 A#		2 C		2 D		2 E		2 F#		2 G#	
Transpose down Result down Blues	2 A# C		2 C	Eb	2 D	F	2 E Gb 1	G 1	2 F#	•	2 G# Bb	
Transpose down Result down Blues Transpose down	2 A# C 2		2 C	Eb	2 D • •	F 2	2 E Gb 1		2 F#		2 G# Bb 3	
Transpose down Result down Blues Transpose down Result down	2 A# C 2 Bb		2 C	Eb	2 D	F 2 Eb	2 E Gb 1 F	G 1 Gb	2 F#		2 G# Bb 3 G	
Transpose down Result down Blues Transpose down Result down Major Pentatonic	2 A# C 2 Bb		2 C	Eb 3 C	2 D • •	F 2 Eb	2 E Gb 1 F	G G G G	2 F#		2 G# Bb 3 G	
Transpose down Result down Blues Transpose down Result down Major Pentatonic Transpose down Result down Minor Pentatonic	2 A# C 2 Bb C 3 A		2 C	Eb 3 C Eb	2 D • • •	F 2 Eb F	2 E Gb 1 F	G G G G G G G G G G G G G G G G G G G	2 F#		2 G# Bb 3 G	
Transpose down Result down Blues Transpose down Result down Major Pentatonic Transpose down Result down	2 A# C 2 Bb		2 C D 2 C	Eb 3 C	2 D • • • E 2 D	F 2 Eb	2 E Gb 1 F	G 1 Gb G 3 E	2 F#		2 G# Bb 3 G	

```
11.2.5.68 const char seq64::c_scales_text[c_scale_size][20]
```

```
11.2.5.69 const char seq64::c_key_text[SEQ64_OCTAVE_SIZE][4]
```

```
11.2.5.70 const char seq64::c_interval_text[16][4]
```

```
11.2.5.71 const char seq64::c_chord_text[8][6]
```

However, we have not seen this menu in the GUI! Ah, it only appears if the user has selected a musical scale like Major or Minor.

```
11.2.5.72 const int seq64::c_max_instruments
```

With a value of 64, this is more of a sanity-check than a realistic number of instruments defined by a user.

```
11.2.5.73 const int seq64::c_max_busses
```

```
11.2.5.74 const std::string seq64::versiontext [static]
```

This value ultimately comes from the configure.ac script.

This was too redundant:

```
SEQ64_PACKAGE " " SEQ64_VERSION " (" SEQ64_GIT_VERSION ") " DATE "\n"
```

```
11.2.5.75 struct option seq64::long_options[] [static]
```

Note the terminating null structure..

```
11.2.5.76 const std::string seq64::s_arg_list [static]
```

The following string keeps track of the characters used so far. An 'x' means the character is used; an 'o' means it is used for the legacy spelling of the option.

Previous arg-list, items missing! "ChVH:IRrb:q:Lni:jJmaAM:pPusSU:x:"

```
11.2.5.77 const char* const seq64::s_help_1a [static]
11.2.5.78 const char* const seq64::s_help_1b [static]
11.2.5.79 const char* const seq64::s_help_2 [static]
11.2.5.80 const char* const seq64::s_help_3 [static]
11.2.5.81 const char* const seq64::s_help_4 [static]
11.2.5.82 const std::string seq64::s_build_highlight_empty [static]
11.2.5.83 const std::string seq64::s_build_lash_support [static]
11.2.5.84 const std::string seq64::s_build_jack_support [static]
11.2.5.85 const std::string seq64::s_build_jack_session [static]
11.2.5.86 const std::string seq64::s_build_pause_support [static]
11.2.5.87 const std::string seq64::s_build_use_event_map [static]
11.2.5.88 const std::string seq64::s_build_chord_generator [static]
11.2.5.89 const std::string seq64::s_build_edit_highlight [static]
11.2.5.90 const std::string seq64::s_build_timesig_tempo [static]
11.2.5.91 const std::string seq64::s_build_midi_vector [static]
11.2.5.92 const std::string seq64::s_build_solid_grid [static]
11.2.5.93 const std::string seq64::s_build_follow_progress [static]
11.2.5.94 const std::string seq64::s_statistics_support [static]
11.2.5.95 struct charpair_t seq64::s_character_mapping[]
11.2.5.96 lash* seq64::s_global_lash_driver [static]
```

It is actually hidden in this module now, so that a function can be used in its place.

Like the font renderer, This item was once created in the main module, sequencer64.cpp. Now we make it a safer, more fool-proof, function. However, unlike the font-render, which always exists, the LASH driver is conditional, and might not be wanted. Therefore, we cannot return a reference, because there's no such thing as a null reference in C++. We have to return a pointer.

```
11.2.5.97 const int seq64::c_status_replace [static]
```

Note how they specify different bit values, as it they could be masked together to signal multiple functions.

This value signals the "replace" functionality.

```
11.2.5.98 const int seq64::c_status_snapshot [static]
11.2.5.99 const int seq64::c_status_queue [static]
11.2.5.100 rc_settings seq64::g_rc_settings [static]
11.2.5.101 user_settings seq64::g_user_settings [static]
11.2.5.102 const long seq64::s_handlesize [static]
11.2.5.103 const int seq64::s_jitter_amount [static]
11.2.5.104 mainwid* seq64::gs_mainwid_pointer [static]
```

We have decided that passing along a mainwnd reference among a number of constructors is too much and actually harder to understand and more error prone. This value is set at the end of the mainwnd constructor, but only the first time that constructor is called.

```
11.2.5.105 const int seq64::c_mainwid_x
```

Affected by the c_mainwid_border and c_mainwid_spacing values.

```
11.2.5.106 const int seq64::c_mainwid_y
11.2.5.107 perfedit* seq64::gs_perfedit_pointer_0 [static]
11.2.5.108 perfedit* seq64::gs_perfedit_pointer_1 [static]
11.2.5.109 const long seq64::s_handlesize [static]
```


Chapter 12

Data Structure Documentation

12.1 seq64::AbstractPerfInput Class Reference

Provides an abstract base class to provide the minimal interface for the various "perf input" classes.

Inheritance diagram for seq64::AbstractPerfInput:



Public Member Functions

AbstractPerfInput ()

Default constructor.

- $\bullet \ \ virtual \sim \! AbstractPerfInput \ ()$
 - Destructor, does nothing.
- virtual bool on_button_press_event (GdkEventButton *a_ev, perfroll &roll)=0
- virtual bool on_button_release_event (GdkEventButton *a_ev, perfroll &roll)=0
- virtual bool on motion notify event (GdkEventMotion *a ev, perfroll &roll)=0

Protected Attributes

• bool m_adding_pressed

Indicates if the left mouse button is pressed while in adding mode.

12.1.1 Constructor & Destructor Documentation

```
12.1.1.1 seq64::AbstractPerfInput::AbstractPerfInput() [inline]
```

12.1.1.2 virtual seq64::AbstractPerfInput::~AbstractPerfInput() [inline], [virtual]

12.1.2 Member Function Documentation

12.1.2.1 virtual bool seq64::AbstractPerfInput::on_button_press_event (GdkEventButton * a_ev, perfroll & roll) [pure virtual]

Implemented in seq64::Seq24PerfInput, and seq64::FruityPerfInput.

12.1.2.2 virtual bool seq64::AbstractPerfInput::on_button_release_event (GdkEventButton * a_ev, perfroll & roll) [pure virtual]

Implemented in seq64::Seq24PerfInput, and seq64::FruityPerfInput.

12.1.2.3 virtual bool seq64::AbstractPerfInput::on_motion_notify_event (GdkEventMotion * a_ev, perfroll & roll) [pure virtual]

Implemented in seq64::Seq24PerfInput, and seq64::FruityPerfInput.

12.1.3 Field Documentation

12.1.3.1 bool seq64::AbstractPerfInput::m_adding_pressed [protected]

12.2 seq64::automutex Class Reference

Provides a mutex that locks automatically when created, and unlocks when destroyed.

Public Member Functions

automutex (mutex &my_mutex)

Principal constructor gets a reference to a mutex parameter, and then locks the mutex.

• ∼automutex ()

The destructor unlocks the mutex.

Private Member Functions

- automutex ()
- automutex (const automutex &)
- automutex & operator= (const automutex &)

Private Attributes

• mutex & m_safety_mutex

Provides the mutex reference to be used for locking.

12.2.1 Detailed Description

This has a couple of benefits. First, it is threadsafe in the face of exception handling. Secondly, it can be done with just one line of code.

12.2.2 Constructor & Destructor Documentation

```
12.2.2.1 seq64::automutex::automutex( ) [private]
```

12.2.2.2 seq64::automutex::automutex (const automutex &) [private]

12.2.2.3 seq64::automutex::automutex (mutex & my_mutex) [inline]

Parameters

```
my_mutex The caller's mutex to be used for locking.
```

```
12.2.2.4 seq64::automutex::~automutex() [inline]
```

12.2.3 Member Function Documentation

12.2.3.1 automutex& seq64::automutex::operator=(const automutex &) [private]

12.2.4 Field Documentation

12.2.4.1 mutex& seq64::automutex::m_safety_mutex [private]

12.3 seq64::click Class Reference

Encapsulates any possible mouse click.

Public Member Functions

· click ()

The constructor for class click.

click (int x, int y, int button=SEQ64_CLICK_BUTTON_LEFT, bool press=true, seq_modifier_t modkey=SE
 — Q64_NO_MASK)

Principal constructor for class click.

• click (const click &rhs)

Provides a stock copy constructor.

click & operator= (const click &rhs)

Provides a stock principal assignment operator.

• bool is press () const

'Getter' function for member m_is_press

· bool is_left () const

'Getter' function for member m_button to test for the left button.

• bool is_middle () const

'Getter' function for member m_button to test for the middle button.

• bool is_right () const

'Getter' function for member m_button to test for the right button.

• int x () const

'Getter' function for member m_x

• int y () const

'Getter' function for member m_y

• int button () const

'Getter' function for member m_button

• seq_modifier_t modifier () const

'Getter' function for member m_modifier

bool mod_control () const

'Getter' function for member m_modifier tested for Ctrl key.

• bool mod_control_shift () const

'Getter' function for member m_modifier tested for Ctrl and Shift key.

• bool mod_super () const

'Getter' function for member m_modifier tested for Mod4/Super/Windows key.

Private Attributes

• bool m_is_press

Determines if the click was a press or a release event.

• int m x

The x-coordinate of the click.

• int m y

The y-coordinate of the click.

• int m_button

The button that was pressed or released.

· seq_modifier_t m_modifier

The optional modifier value.

12.3.1 Detailed Description

Useful in passing more generic events to non-GUI classes.

12.3.2 Constructor & Destructor Documentation

```
12.3.2.1 seq64::click::click()
```

Sets all members to false, zero, or the lowest good value.

```
12.3.2.2 seq64::click::click ( int x, int y, int button = SEQ64_CLICK_BUTTON_LEFT, bool press = true, seq_modifier_t modkey = SEQ64_NO_MASK )
```

This function is the only way to set value for the click members (other than the copy constructor and principal assignment operator.

Parameters

X	The putative x value of the button click.					
У	The putative y value of the button click.					
button	The value of the button that was clicked, set to 1, 2, or 3.					
press	Set to true if the event was a button press, false if it was a button release.					
modkey	Indicates which modifier key (such as Ctrl or Alt), if any, was pressed at the same time as the click					
	action.					

12.3.2.3 seq64::click::click (const click & rhs)

It is nice to be explicit about these kinds of functions, even if it gets tedious.

Parameters

rhs	Provies the source object to be copied.
-----	---

12.3.3 Member Function Documentation

12.3.3.1 click & seq64::click::operator= (const click & rhs)

It is nice to be explicit about these kinds of functions, even if it gets tedious.

Parameters

rhs	Provies the source object to be assigned from. The assignment is not made if "this" has the same
	address as this parameter.

Returns

Returns a reference to self for usage in a string of assignments.

```
12.3.3.2 bool seq64::click::is_press() const [inline]
12.3.3.3 bool seq64::click::is_left( ) const [inline]
12.3.3.4 bool seq64::click::is_middle( ) const [inline]
12.3.3.5 bool seq64::click::is_right( ) const [inline]
12.3.3.6 int seq64::click::x( ) const [inline]
12.3.3.7 int seq64::click::y( )const [inline]
12.3.3.8 int seq64::click::button() const [inline]
12.3.3.9 seq_modifier_t seq64::click::modifier() const [inline]
12.3.3.10 bool seq64::click::mod_control() const [inline]
12.3.3.11 bool seq64::click::mod_control_shift( ) const [inline]
12.3.3.12 bool seq64::click::mod_super( ) const [inline]
12.3.4 Field Documentation
12.3.4.1 bool seq64::click::m_is_press [private]
12.3.4.2 int seq64::click::m_x [private]
0 is the left-most coordinate.
12.3.4.3 int seq64::click::m_y [private]
0 is the top-most coordinate.
12.3.4.4 int seq64::click::m_button [private]
```

Left is 1, mmiddle is 2, and right is 3. These numbers are defined via macros, and are Linux-specific and Gtk-specific.


12.3.4.5 seq_modifier_t seq64::click::m_modifier [private]

Note that SEQ64_NO_MASK is our word for 0, meaning "no modifier".

12.4 seq64::condition_var Class Reference

A mutex works best in conjunction with a condition variable.

Inheritance diagram for seq64::condition_var:



Public Member Functions

• condition_var ()

Initialize the condition variable with the global variable.

• void wait ()

Waits for the condition variable.

• void signal ()

Signals the condition variable.

Private Attributes

• pthread_cond_t m_cond

Provides a class-specific condition variable.

Static Private Attributes

static const pthread_cond_t sm_cond
 Provides a "global" condition variable.

Additional Inherited Members

12.4.1 Detailed Description

Therefore this class derives from the mutex class. A "has-a" relationship might be more logical than this "is-a" relationship.

12.4.2 Constructor & Destructor Documentation

```
12.4.2.1 seq64::condition_var::condition_var( )
```

12.4.3 Member Function Documentation

```
12.4.3.1 void seq64::condition_var::wait ( )
```

12.4.3.2 void seq64::condition_var::signal ()

12.4.4 Field Documentation

```
12.4.4.1 const pthread_cond_t seq64::condition_var::sm_cond [static], [private]
```


Define the static condition variable used by all mutex locks.

12.4.4.2 pthread_cond_t seq64::condition_var::m_cond [private]

12.5 seq64::configfile Class Reference

This class is the abstract base class for optionsfile and userfile.

Inheritance diagram for seq64::configfile:



Public Member Functions

• configfile (const std::string &name)

Provides the string constructor for a configuration file.

virtual ∼configfile ()

A rote destructor needed for a base class.

- virtual bool parse (perform &perf)=0
- virtual bool write (const perform &perf)=0

Protected Member Functions

• bool next_data_line (std::ifstream &file)

Gets the next line of data from an input stream.

• void line_after (std::ifstream &file, const std::string &tag)

This function gets a specific line of text, specified as a tag.

Protected Attributes

• std::string m_name

Provides the name of the configuration file.

char * m_d

Points to an allocated buffer that holds the data for the configuration file.

• char m_line [SEQ64_LINE_MAX]

The current line of text being processed.

12.5.1 Constructor & Destructor Documentation

12.5.1.1 seq64::configfile::configfile (const std::string & name)

Parameters

name	The name of the configuration file.
------	-------------------------------------

12.5.1.2 virtual seq64::configfile::~configfile() [inline], [virtual]

12.5.2 Member Function Documentation

12.5.2.1 bool seq64::configfile::next_data_line(std::ifstream & file) [protected]

If the line starts with a number-sign, a space (!), or a null, it is skipped, to try the next line. This occurs until an EOF is encountered.

Member m_line is a "global" return value.

Parameters

file Points to an input stream. We converted this item to a reference; pointers can be subject to problems. For example, what if someone passes a null pointer?

Returns

Returns true if a presumed data line was found. False is returned if not found before an EOF or a section marker ("[") is found. This is a a new (ca 2016-02-14) feature of this function, to assist in adding new data to the file.

12.5.2.2 void seq64::configfile::line_after (std::ifstream & file, const std::string & tag) [protected]

Then it gets the next non-blank line (i.e. data line) after that.


Parameters

file	Points to the input file stream.
tag	Provides a tag to be found. Lines are read until a match occurs with this tag. Normally, the tag is a
	section marker, such as "[user-interface]". Best to assume an exact match is needed.

```
12.5.2.3 virtual bool seq64::configfile::parse ( perform & perf ) [pure virtual]
Implemented in seq64::optionsfile, and seq64::userfile.
12.5.2.4 virtual bool seq64::configfile::write ( const perform & perf ) [pure virtual]
Implemented in seq64::optionsfile, and seq64::userfile.
12.5.3 Field Documentation
12.5.3.1 std::string seq64::configfile::m_name [protected]
12.5.3.2 char* seq64::configfile::m_d [protected]
12.5.3.3 char seq64::configfile::m_line[SEQ64_LINE_MAX] [protected]
This member receives an input line, and so needs to be a character buffer.
       seq64::editable_event Class Reference
12.6
```

Provides for the management of MIDI editable events.

Inheritance diagram for seq64::editable_event:



Data Structures

· struct name value t

Provides a type that contains the pair of values needed for the various lookup maps that are needed to manage editable events.

Public Types

Public Member Functions

editable_event (const editable_events &parent)

This constructor simply initializes all of the class members.

editable_event (const editable_events &parent, const event &ev)

Event constructor.

editable event (const editable event &rhs)

This copy constructor initializes most of the class members.

- editable_event & operator= (const editable_event &rhs)
- virtual ∼editable event ()

This destructor current is a rote virtual function override.

· const editable_events & parent () const

'Getter' function for member m_parent

· category_t category () const

'Getter' function for member m_category

void category (category_t c)

'Setter' function for member m_category by value Also keeps the m_name_category member in synchrony.

· const std::string & category_string () const

'Getter' function for member m_category

void category (const std::string &cs)

'Setter' function for member m_category by name Also keeps the m_name_category member in synchrony, but looks up the name, rather than using the name parameter, to avoid storing abbreviations.

const std::string & timestamp string () const

'Getter' function for member m_name_timestamp

midipulse timestamp () const

'Getter' function for member event::get_timestamp() Implemented to allow a uniform naming convention that is not slavish to the get/set crowd [this ain't Java].

• void timestamp (midipulse ts)

'Setter' function for member event::set_timestamp() Implemented to allow a uniform naming convention that is not slavish to the get/set crowd [this ain't Java].

void timestamp (const std::string &ts_string)

'Setter' function for member event::set_timestamp() [string version]

std::string time_as_pulses ()

Converts the current time-stamp to a string representation in units of pulses.

• std::string time_as_measures ()

Converts the current time-stamp to a string representation in units of measures, beats, and divisions.

std::string time_as_minutes ()

Converts the current time-stamp to a string representation in units of hours, minutes, seconds, and fraction.

void set_status_from_string (const std::string &ts, const std::string &s, const std::string &sd0, const std::string &sd1)

Converts a string into an event status, along with timestamp and data bytes.

• std::string format timestamp ()

Formats the current timestamp member as a string.

• std::string stock_event_string ()

Converts the event into a string desribing the full event.

• std::string status_string () const

'Getter' function for member m_name_status

std::string meta_string () const

'Getter' function for member m_name_meta

std::string seqspec_string () const

'Getter' function for member m_name_seqspec

std::string channel string () const

'Getter' function for member m_name_channel

std::string data_string () const

'Getter' function for member m_name_data

Static Public Member Functions

• static std::string value_to_name (midibyte value, category_t cat)

Provides a static lookup function that returns the name, if any, associated with a midibyte value.

static unsigned short name_to_value (const std::string &name, category_t cat)

Provides a static lookup function that returns the value, if any, associated with a name string.

Static Public Attributes

static const name value t sm category names []

An array of event categories and their names.

static const name_value_t sm_channel_event_names[]

An array of MIDI channel events and their names.

static const name_value_t sm_system_event_names []

An array of MIDI system events and their names.

static const name_value_t sm_meta_event_names []

An array of Meta events and their names.

static const name_value_t sm_prop_event_names[]

An array of Sequencer64-specific events and their names.

static const name_value_t *const sm_category_arrays[]

Provides for fast access (no ifs) to the correct name array for the given category.

Private Member Functions

- editable_event ()
- · void analyze ()

Analyzes an editable-event to make all the settings it needs.

Private Attributes

· const editable_events & m_parent

Provides a reference to the container that holds this event.

category_t m_category

Indicates the overall category of this event, which will be category_channel_message, category_system_message, category_meta_event, and category_prop_event.

std::string m_name_category

Holds the name of the event category for this event.

timestamp_format_t m_format_timestamp

Indicates the format to display the time-stamp.

std::string m name timestamp

Holds the string version of the MIDI pulses time-stamp.

std::string m_name_status

Holds the name of the status value for this event.

· std::string m name meta

Holds the name of the meta message, if applicable.

std::string m_name_seqspec

If we eventually implement the editing of the Seq24/Sequencer64 "proprietary" meta sequencer-specific events, the name of the SeqSpec will be stored here.

std::string m name channel

Holds the channel description, if applicable.

std::string m_name_data

Holds the data description, if applicable.

12.6.1 Detailed Description

It makes the following members of an event modifiable using human-readable strings:

- m_timestamp
- m_status
- m_channel
- m_data[]

Eventually, it would be nice to be able to edit, or at least view, the SysEx events and the Meta events. Those two will require extensions to make events out of them (SysEx is partly supported).

To the concepts of event, the editable_event class adds a category field and strings to represent all of these members.

12.6.2 Member Enumeration Documentation

12.6.2.1 enum seq64::editable_event::category_t

These tags are accompanied by category names in sm_category_names[]. The enum values are cast to midibyte values for the purposes of using the lookup infrastructure.

Enumerator

- *category_name* Indicates that the lookup needs to be done on the category names, as listed in sm_← category_names[].
- **category_channel_message** Indicates a channel event, with a value ranging from 0x80 through 0xEF. Some examples are note on/off, control change, and program change. Values are looked up in sm_← channel_event_names[].
- category_system_message Indicates a system event, with a value ranging from 0xF0 through 0xFF. Some examples are SysEx start/end, song position, and stop/start/continue/reset. Values are looked up in sm_system_event_names[].
- **category_meta_event** Indicates a meta event, and there is a second value that is used to look up the name of the meta event, in sm meta event names[].
- category_prop_event Indicates a "proprietary", Sequencer64 event. Indicates to look up the name of the event in sm_prop_event_names[]. Not sure if these kinds of events will be stored separately.

12.6.2.2 enum seq64::editable_event::timestamp_format_t

Three are supported. All editable events will share the same timestamp format, but it seems good to make this a event class member, rather than something imposed from an outside static value. We shall see.

Enumerator

timestamp_measures This format displays the time in "measures:beats:divisions" format, where measures and beats start at 1. Thus, "1:1:0" is equivalent to 0 pulses or to "0:0:0:0.0" in normal time values.

timestamp_time This format displays the time in "hh:mm:second.fraction" format. The value displayed should not depend upon the internal timing parameters of the event.

timestamp_pulses This format specifies a bare pulse format for the timestamp – a long integer ranging from 0 on up. Obviously, this representation depends on the PPQN value for the sequence holding this event.

12.6.3 Constructor & Destructor Documentation

```
12.6.3.1 seq64::editable_event::editable_event( ) [private]
```

12.6.3.2 seq64::editable_event::editable_event (const editable_events & parent)

editable_event::editable_event (): event (), m_category (category_name), m_name_category (), m_format_
timestamp (timestamp_measures), m_name_timestamp (), m_name_status (), m_name_meta (), m_name_
seqspec (), m_name_channel (), m_name_data () { // Empty body } Principal constructor.

Parameters

parent Provides the overall editable-events object that manages the whole set of editable-event.

12.6.3.3 seq64::editable_event::editable_event (const editable_events & parent, const event & ev)

This function basically adds all of the extra editable_event stuff to a standard event, so that the resulting editable event is container-ready.

12.6.3.4 seq64::editable_event::editable_event (const editable_event & rhs)

This function is currently geared only toward support of the SMF 0 channel-splitting feature. Many of the members are not set to useful values when the MIDI file is read, so we don't handle them for now.

Warning

This function does not yet copy the SysEx data. The inclusion of SysEx editable_events was not complete in Seq24, and it is still not complete in Sequencer64. Nor does it currently bother with the links.

Parameters

rhs | Provides the editable_event object to be copied.

- 12.6.3.5 virtual seq64::editable_event::~editable_event() [inline], [virtual]
- 12.6.4 Member Function Documentation
- 12.6.4.1 std::string seq64::editable_event::value_to_name (midibyte value, editable_event::category_t cat) [static]

Parameters

	value	The MIDI byte value to look up.	
ſ	cat	The category of the MIDI byte. Each category calls a different name array into play.	

Returns

Returns the name associated with the value. If there is no such name, then an empty string is returned.

12.6.4.2 unsigned short seq64::editable_event::name_to_value (const std::string & name, editable_event::category_t cat
) [static]

The string_match() function, which can match abbreviations, case-insensitively, is used to make the string comparisons.

Parameters

name	The string value to look up.
cat	The category of the MIDI byte. Each category calls a different name array into play.

Returns

Returns the value associated with the name. If there is no such value, then SEQ64_END_OF_MIDIBYTE $_{\leftarrow}$ TABLE is returned.

- 12.6.4.3 editable_event & seq64::editable_event::operator= (const editable_event & rhs)
- 12.6.4.4 const editable_events& seq64::editable_event::parent() const [inline]
- 12.6.4.5 category_t seq64::editable_event::category()const [inline]
- 12.6.4.6 void seq64::editable_event::category (category_t c)

Note that a bad value is translated to the value of category name.

Parameters

c Provides the category value to set.

```
12.6.4.7 const std::string& seq64::editable_event::category_string( ) const [inline]
```

12.6.4.8 void seq64::editable_event::category (const std::string & name)

Note that a bad value is translated to the value of category_name.

Parameters

```
12.6.4.9 const std::string& seq64::editable_event::timestamp_string( ) const [inline]

12.6.4.10 midipulse seq64::editable_event::timestamp( ) const [inline]
```

Plus, we also have to set the string version at the same time.

12.6.4.11 void seq64::editable_event::timestamp (midipulse ts)

The format of the string representation is of the format selected by the m_format_timestamp member and is set by the format_timestamp() function.

Parameters

ts Provides the timestamp in units of MIDI pulses.

12.6.4.12 void seq64::editable_event::timestamp (const std::string & ts_string)

The format of the string representation is of the format selected by the m_format_timestamp member and is set by the format_timestamp() function.

Parameters

ts_string	Provides the timestamp in units of MIDI pulses.

```
12.6.4.13 std::string seq64::editable_event::time_as_pulses() [inline]
```

12.6.4.14 std::string seq64::editable_event::time_as_measures ()

Cannot be inlined because of a circular dependency between the editable event and editable events classes.

12.6.4.15 std::string seq64::editable_event::time_as_minutes ()

Cannot be inlined because of a circular dependency between the editable_event and editable_events classes.

12.6.4.16 void seq64::editable_event::set_status_from_string (const std::string & ts, const std::string & s, const std::string & sd0, const std::string & sd1)

Currently, this function handles only the following two messages:

- · category_channel_message
- · category_system_message

After all of the numbering member items have been set, they are converted and assigned to the string versions via a call to the analyze() function.

Parameters

ts	Provides the time-stamp string of the event.	
s	Provides the name of the event, such as "Program Change".	
sd0 Provides the string defining the first data byte of the event.		
sd1	Provides the string defining the second data byte of the event, if applicable to the event.	

```
12.6.4.17 std::string seq64::editable_event::format_timestamp()
```

The format of the string representation is of the format selected by the m_format_timestamp member.

```
12.6.4.18 std::string seq64::editable_event::stock_event_string()
```

We get the time-stamp as a string, make sure the event is fully analyzed so that all items and strings are set correctly.

Returns

Returns a human-readable string describing this event.

```
12.6.4.20 std::string seq64::editable_event::meta_string() const [inline]

12.6.4.21 std::string seq64::editable_event::seqspec_string() const [inline]

12.6.4.22 std::string seq64::editable_event::channel_string() const [inline]

12.6.4.23 std::string seq64::editable_event::data_string() const [inline]

12.6.4.24 void seq64::editable_event::analyze() [private]
```

Used in the constructors. Some of the setters indirectly set the appropriate string representation, as well.

Category:

This function can figure out if the status byte implies a channel message or a system message, and set the category string as well. However, at this time, detection of Meta events (0xFF) or Proprietary/SeqSpec events (0xFF with 0x2424) doesn't work due to lack of context here (and due to the fact that currently such events are not yet stored in a Sequencer64 sequence/track, and the least-significant-byte gets masked off anyway.)

Status:

We distinguish between channel and system messages, and then one— and two-byte messages, but don't yet distinguish the data values fully.

12.6.5 Field Documentation

12.6.5.1 const editable_event::name_value_t seq64::editable_event::sm_category_names [static]

Initializes the array of event/name pairs for the MIDI events categories.

Terminated by an empty string, the latter being the preferred test, for consistency with the other arrays and because 0 is often a legitimate code value.

12.6.5.2 const editable_event::name_value_t seq64::editable_event::sm_channel_event_names [static]

Initializes the array of event/name pairs for the channel MIDI events.

We split channel and system messages into two arrays, for semantic reasons and for faster linear lookups.

Terminated by an empty string.

12.6.5.3 const editable_event::name_value_t seq64::editable_event::sm_system_event_names [static]

Initializes the array of event/name pairs for the system MIDI events.

We split channel and system messages into two arrays, for semantic reasons and for faster linear lookups.

Terminated by an empty string.

12.6.5.4 const editable_event::name_value_t seq64::editable_event::sm_meta_event_names [static]

Initializes the array of event/name pairs for all of the Meta events.

Terminated only by the empty string.

12.6.5.5 const editable_event::name_value_t seq64::editable_event::sm_prop_event_names [static]

Initializes the array of event/name pairs for all of the seq24/sequencer64-specific events.

Terminated only by the empty string. Note that the numbers reflect the masking off of the high-order bits by 0x242400FF.

```
12.6.5.6 const editable_event::name_value_t *const seq64::editable_event::sm_category_arrays [static]
```

Contains pointers (references cannot be stored in an array) to the desired array for a given category.

Too bad that an array of references is not possible.

This code could be considered a bit rococo.

```
12.6.5.7 const editable_events& seq64::editable_event::m_parent [private]
```

The container's "children" need to go to their "parent" to get certain items of information.

```
12.6.5.8 category_t seq64::editable_event::m_category [private]
```

The category_name value is not set here, since that category is used only for looking up the human-readable form of the category.

```
12.6.5.9 std::string seq64::editable_event::m_name_category [private]
```

```
12.6.5.10 timestamp_format_t seq64::editable_event::m_format_timestamp [private]
```

The default is to display in timestamp measures format.

```
12.6.5.11 std::string seq64::editable_event::m_name_timestamp [private]
```

```
12.6.5.12 std::string seq64::editable_event::m_name_status [private]
```

It will include the names of the channel messages and the system messages. The latter includes SysEx and Meta messages.

```
12.6.5.13 std::string seq64::editable_event::m_name_meta [private]
```

If not applicable, this name will be empty.

```
12.6.5.14 std::string seq64::editable_event::m_name_seqspec [private]
```

```
12.6.5.15 std::string seq64::editable_event::m_name_channel [private]
```

```
12.6.5.16 std::string seq64::editable_event::m_name_data [private]
```

12.7 seg64::editable events Class Reference

Provides for the management of an ordered collection MIDI editable events.

Public Member Functions

editable_events (sequence &seq, int bpm)

This constructor hooks into the sequence object.

editable_events (const editable_events &rhs)

This copy constructor initializes most of the class members.

editable_events & operator= (const editable_events &rhs)

This principal assignment operator sets most of the class members.

virtual ∼editable events ()

This destructor current is a rote virtual function override.

• const midi_timing & timing () const

'Getter' function for member m_midi_parameters

· midipulse string_to_pulses (const std::string &ts_string) const

Calculates the MIDI pulses (divisions) from a string using one of the free functions of the calculations module.

• bool load events ()

Accesses the sequence's event-list, iterating through it from beginning to end, wrapping each event in the list in an editable event and inserting it into the editable-event container.

• bool save events ()

Erases the sequence's event container and recreates it using the edited container of editable events.

· Events & events ()

'Getter' function for member m_events

· iterator begin ()

'Getter' function for member m_events.begin(), non-constant version.

· const_iterator begin () const

'Getter' function for member m_events.begin(), constant version.

· iterator end ()

'Getter' function for member m_events.end(), non-constant version.

· const_iterator end () const

'Getter' function for member m_events.end(), constant version.

int count () const

Returns the number of events stored in m events.

• bool add (const event &e)

Adds an event, converted to an editable_event, to the internal event list.

• bool add (const editable_event &e)

Adds an editable event to the internal event list.

• bool replace (iterator ie, const editable_event &e)

Provides a wrapper for the iterator form of erase(), which is the only one that the editable_events container uses.

• void remove (iterator ie)

Provides a wrapper for the iterator form of erase(), which is the only one that sequence uses.

• void clear ()

Provides a wrapper for clear().

iterator current_event () const

'Getter' function for member m_current_event The caller must make sure the iterator is not Events::end().

Static Public Member Functions

• static editable_event & dref (iterator ie)

Dereference access for list or map.

static const editable_event & dref (const_iterator ie)

Dereference const access for list or map.

Private Types

- typedef event list::event key Key
 - Types to use to with the multimap implementation.
- typedef std::pair< Key, editable event > EventsPair
- typedef std::multimap< Key, editable_event > Events
- typedef std::multimap< Key, editable_event >::iterator iterator
- typedef std::multimap< Key, editable_event >::const_iterator const_iterator

Private Member Functions

- · editable events ()
- · void current event (iterator cei)

'Setter' function for member m_current_event

Private Attributes

Events m_events

Holds the editable_events.

• iterator m_current_event

Points to the current event, which is the event that has just been inserted.

sequence & m_sequence

Provides a reference to the sequence containing the events to be edited.

• midi_timing m_midi_parameters

Holds the current settings for the sequence (and usually for the whole MIDI tune as well).

Friends

· class eventslots

12.7.1 Member Typedef Documentation

```
12.7.1.1 typedef event_list::event_key seq64::editable_events::Key [private]
```

These typenames are identical to those used in event_list, but of course they are in the editable_events scope instead. See the event_list class.

```
12.7.1.2 typedef std::pair < Key, editable event > seq64::editable events::EventsPair [private]
```

- 12.7.1.3 typedef std::multimap<Key, editable_event> seq64::editable_events::Events [private]
- 12.7.1.4 typedef std::multimap < Key, editable_event >::iterator seq64::editable_events::iterator [private]
- 12.7.1.5 typedef std::multimap<Key, editable_event>::const_iterator seq64::editable_events::const_iterator [private]

12.7.2 Constructor & Destructor Documentation

```
12.7.2.1 seq64::editable_events::editable_events() [private]
```

12.7.2.2 seq64::editable_events::editable_events (sequence & seq, int bpm)

Parameters

	seq	Provides a reference to the sequence object, which provides the events and some of the MIDI timing parameters.	1
Ì	bpm	Provides the beats/minute value, which the caller figures out how to get and provides in this parameter.	1

12.7.2.3 seq64::editable_events::editable_events (const editable_events & rhs)

Note that we need to reconstitute the event links here, as well.

Parameters

rhs	Provides the editable	events object to be copied.
-----	-----------------------	-----------------------------

- **12.7.2.4** virtual seq64::editable_events::~editable_events() [inline], [virtual]
- 12.7.3 Member Function Documentation
- 12.7.3.1 editable_events & seq64::editable_events::operator= (const editable_events & rhs)

Note that we need to reconstitute the event links here, as well.

Parameters

rhs Provides the editable_events object to be assigned.

Returns

Returns a reference to "this" object, to support the serial assignment of editable_eventss.

- 12.7.3.2 const midi_timing& seq64::editable_events::timing() const [inline]
- 12.7.3.3 midipulse seq64::editable_events::string_to_pulses (const std::string & ts_string) const [inline]
- 12.7.3.4 bool seq64::editable_events::load_events()

Note that the new events will not have valid links (actually, no links). These links are used for associating Note Off events with their respective Note On events. To be consistent, we must take the time to reconstitute these links, using event_list::verify_and_link().

Returns

Returns true if the size of the final editable_event container matches the size of the original events container.

```
12.7.3.5 bool seq64::editable_events::save_events()
```

Note that the old events are replaced only if the container of editable events is not empty. There are safer ways for the user to erase all the events.

Todo Consider what to do about the sequence::m_is_modified flag.

Returns

Returns true if the size of the final event container matches the size of the original editable events container.

```
12.7.3.6 Events& seq64::editable_events::events() [inline]

12.7.3.7 iterator seq64::editable_events::begin() const [inline]

12.7.3.8 const_iterator seq64::editable_events::begin() const [inline]

12.7.3.9 iterator seq64::editable_events::end() [inline]

12.7.3.10 const_iterator seq64::editable_events::end() const [inline]

12.7.3.11 static editable_event& seq64::editable_events::dref(iterator ie) [inline], [static]

Parameters

ie Provides the iterator to the event to which to get a reference.
```

12.7.3.12 static const editable_event& seq64::editable_events::dref(const_iterator ie) [inline], [static]

Parameters

ie Provides the iterator to the event to which to get a reference.

```
12.7.3.13 int seq64::editable_events::count() const [inline]
```

We like returning an integer instead of size_t, and rename the function so nobody is fooled.

12.7.3.14 bool seq64::editable_events::add (const event & e)

Parameters

e Provides the regular event to be added to the list of editable events.

Returns

Returns true if the insertion succeeded, as evidenced by an increment in container size.

```
12.7.3.15 bool seq64::editable_events::add ( const editable_event & e )
```

For the std::multimap implementation, This is an option if we want to make sure the insertion succeed.

```
std::pair<Events::iterator, bool> result = m_events.insert(p);
return result.second;
```

Parameters

Provides the regular event to be added to the list of editable events.

Returns

Returns true if the insertion succeeded, as evidenced by an increment in container size.

Side-effect(s) Sets m_current_event, which can be used right-away in a single-threaded context to get an iterator to the event via the current_event() accessor.

```
12.7.3.16 bool seq64::editable_events::replace ( iterator ie, const editable_event & e ) [inline]
12.7.3.17 void seq64::editable_events::remove ( iterator ie ) [inline]
12.7.3.18 void seq64::editable_events::clear ( ) [inline]
12.7.3.19 iterator seq64::editable_events::current_event ( ) const [inline]
12.7.3.20 void seq64::editable_events::current_event ( iterator cei ) [inline], [private]
```

Parameters

cei Provide an iterator to the event to set as the current event.


12.7.4 Friends And Related Function Documentation

- **12.7.4.1** friend class eventslots [friend]
- 12.7.5 Field Documentation
- **12.7.5.1 Events seq64::editable_events::m_events** [private]
- **12.7.5.2** iterator seq64::editable_events::m_current_event [private]

(From this event we can get the current time and other parameters.) If the container were a plain map, we could instead use a key to access it. But we can at least use an iterator, rather than a bare pointer.

12.7.5.3	3 sequence& seq64::editable_events::m_sequence [priva	te]
	es the events, this object also holds the beats/measure, be to be obtained from the application's perform object, and p	
12.7.5.4	4 midi_timing seq64::editable_events::m_midi_parameters [orivate]
	ds the beats/minute, beats/measure, beat-width, and PPQ tamps to time and measure values.	N values needed to properly convert MIDI pulse
12.8	seq64::event Class Reference	
Provides	des events for management of MIDI events.	

Inheritance diagram for seq64::event:



Public Types

• typedef std::vector< midibyte > SysexContainer

Provides a type definition for a vector of midibytes.

Public Member Functions

event ()

This constructor simply initializes all of the class members.

• event (const event &rhs)

This copy constructor initializes most of the class members.

event & operator= (const event &rhs)

This principal assignment operator sets most of the class members.

virtual ~event ()

This destructor explicitly deletes m_sysex and sets it to null.

bool operator< (const event &rhsevent) const

If the current timestamp equal the event's timestamp, then this function returns true if the current rank is less than the event's rank.

void set timestamp (midipulse time)

'Setter' function for member m_timestamp

• midipulse get_timestamp () const

'Getter' function for member m timestamp

• midibyte get_channel () const

'Getter' function for member m_channel

· bool check_channel (int channel) const

Checks the channel number to see if the event's channel matches it, or if the event has no channel.

void mod_timestamp (midipulse modtick)

Calculates the value of the current timestamp modulo the given parameter.

• void set_status (midibyte status)

Sets the m_status member to the value of status.

· void set status (midibyte eventcode, midibyte channel)

This overload is useful when synthesizing events, such as converting a Note On event with a velocity of zero to a Note Off event

void set_status_keep_channel (midibyte eventcode)

This function is used in recording to preserve the input channel information for deciding what to do with an incoming MIDI event.

void set_channel (midibyte channel)

Sets the channel "nybble", without modifying the status "nybble".

midibyte get_status () const

'Getter' function for member m_status

void set_data (midibyte d1)

Clears the most-significant-bit of the d1 parameter, and sets it into the first byte of m_data.

void set_data (midibyte d1, midibyte d2)

 ${\it Clears the most-significant-bit of both parameters, and sets them into the first and second bytes of {\it m_data}.}$

void get_data (midibyte &d0, midibyte &d1) const

Retrieves the two data bytes from m_data[] and copies each into its respective parameter.

void increment_data1 ()

Increments the first data byte (m_data[0]) and clears the most significant bit.

void decrement_data1 ()

Decrements the first data byte (m_data[0]) and clears the most significant bit.

void increment_data2 ()

Increments the second data byte (m_data[1]) and clears the most significant bit.

void decrement_data2 ()

Decrements the second data byte (m_data[1]) and clears the most significant bit.

bool append sysex (midibyte *data, int len)

Appends SYSEX data to a new buffer.

bool append_sysex (midibyte data)

An overload for obtaining SYSEX data byte-by-byte.

void restart_sysex ()

Deletes and clears out the SYSEX buffer.

SysexContainer & get_sysex ()

'Getter' function for member m_sysex from stazed, non-const version for use by midibus.

const SysexContainer & get_sysex () const

'Getter' function for member m_sysex from stazed

void set_sysex_size (int len)

'Setter' function for member m_sysex and m_sysex_size from stazed

• int get_sysex_size () const

'Getter' function for member m_sysex_size

void link (event *ev)

Sets m_has_link and sets m_link to the provided event pointer.

event * get_linked () const

'Getter' function for member m_linked

· bool is_linked () const

'Getter' function for member m_has_link

· void clear link ()

'Setter' function for member m_has_link

• void paint ()

'Setter' function for member m_painted

void unpaint ()

'Setter' function for member m_painted

• bool is_painted () const

'Getter' function for member m_painted

· void mark ()

 ${\it 'Setter' function for member m_marked}$

• void unmark ()

'Setter' function for member m_marked

bool is_marked () const

'Getter' function for member m_marked

• void select ()

'Setter' function for member m_selected

void unselect ()

'Setter' function for member m_selected

bool is_selected () const

'Getter' function for member $m_selected$

void make_clock ()

Sets m_status to EVENT_MIDI_CLOCK;.

· midibyte data (int index) const

'Getter' function for member m_data[]

midibyte get_note () const

Assuming m_data[] holds a note, get the note number, which is in the first data byte, m_data[0].

void set_note (midibyte note)

Sets the note number, clearing off the most-significant-bit and assigning it to the first data byte, m_data[0].

• midibyte get_note_velocity () const

'Getter' function for member m_data[1], the note velocity.

void set_note_velocity (int vel)

Sets the note velocity, which is held in the second data byte, and clearing off the most-significant-bit, storing it in m_{data} [1].

• bool is_note_on () const

Check for the Note On value in m_status.

bool is_note_off () const

Check for the Note Off value in m status.

• bool is_note () const

Returns true if m_status is a Note On, Note Off, or Aftertouch message.

• bool is_note_off_recorded () const

Some keyboards send Note On with velocity 0 for Note Off, so we provide this function to test that during recording.

· void print () const

Prints out the timestamp, data size, the current status byte, any SYSEX data if present, or the two data bytes for the status byte.

• int get_rank () const

This function is used in sorting MIDI status events (e.g.

Static Public Member Functions

static bool is channel msg (midibyte m)

Static test for the channel message/statuse values: Note On, Note Off, Aftertouch, Control Change, Program Change, Channel Pressure, and Pitch Wheel.

static bool is_one_byte_msg (midibyte m)

Static test for channel messages that have only one data byte: Program Change and Channel Pressure.

static bool is_two_byte_msg (midibyte m)

Static test for channel messages that have two data bytes: Note On, Note Off, Control Change, Aftertouch, and Pitch Wheel.

static bool is_note_msg (midibyte m)

Static test for messages that involve notes and velocity: Note On, Note Off, and Aftertouch.

static bool is_strict_note_msg (midibyte m)

Static test for messages that involve notes only: Note On and Note Off.

• static bool is_desired_cc_or_not_cc (midibyte m, midibyte cc, midibyte datum)

Static test for channel messages that are either not control-change messages, or are and match the given controller value.

Private Attributes

• midipulse m_timestamp

Provides the MIDI timestamp in ticks, otherwise known as the "pulses" in "pulses per quarter note" (PPQN).

· midibyte m_status

This is the status byte without the channel.

· midibyte m channel

In order to be able to handle MIDI channel-splitting of an SMF 0 file, we need to store the channel, even if we override it when playing the MIDI data.

midibyte m_data [SEQ64_MIDI_DATA_BYTE_COUNT]

The two bytes of data for the MIDI event.

• SysexContainer m_sysex

The data buffer for SYSEX messages.

• int m_sysex_size

Gives the size of the SYSEX message.

• event * m_linked

This event is used to link Note Ons and Offs together.

bool m_has_link

Indicates that a link has been made.

· bool m_selected

Answers the question "is this event selected in editing.".

· bool m marked

Answers the question "is this event marked in processing.".

· bool m_painted

Answers the question "is this event being painted.".

12.8.1 Detailed Description

A MIDI event consists of 3 bytes:

```
-# Status byte, 1sssnnn, where the sss bits specify the type of
message, and the nnnn bits denote the channel number.
The status byte always starts with 0.
```

- -# The first data byte, 0xxxxxxx, where the data byte always start with 0, and the xxxxxxx values range from 0 to 127.
- -# The second data byte, 0xxxxxxx.

This class may have too many member functions.

12.8.2 Member Typedef Documentation

12.8.2.1 typedef std::vector<midibyte> seq64::event::SysexContainer

12.8.3 Constructor & Destructor Documentation

```
12.8.3.1 seq64::event::event()
```

12.8.3.2 seq64::event::event (const event & rhs)

This function is currently geared only toward support of the SMF 0 channel-splitting feature. Many of the members are not set to useful values when the MIDI file is read, so we don't handle them for now.

Note that now events are also copied when creating the editable_events container, so this function is even more important. The event links, for linking Note Off events to their respective Note On events, are dropped. Generally, they will need to be reconstituted by calling the event_list::verify_and_link() function.

Warning

This function does not yet copy the SysEx data. The inclusion of SysEx events was not complete in Seq24, and it is still not complete in Sequencer64. Nor does it currently bother with the links, as noted above.

Parameters

rhs Provides the event object to be copied.

```
12.8.3.3 seq64::event::~event() [virtual]
```

The restart sysex() function does what we need. But now that m sysex is a vector, no action is needed.

12.8.4 Member Function Documentation

12.8.4.1 event & seq64::event::operator= (const event & rhs)

This function is currently geared only toward support of the SMF 0 channel-splitting feature. Many of the member are not set to useful value when the MIDI file is read, so we don't handle them for now.

Warning

This function now copies the SysEx data, but the inclusion of SysEx events was not complete in Seq24, and it is still not complete in Sequencer64. Nor does it currently bother with the link the event might have.

Parameters

rhs Provides the event object to be assigned.

Returns

Returns a reference to "this" object, to support the serial assignment of events.

12.8.4.2 bool seq64::event::operator< (const event & rhs) const

Otherwise, it returns true if the current timestamp is less than the event's timestamp.

Warning

The less-than operator is supposed to support a "strict weak ordering", and is supposed to leave equivalent values in the same order they were before the sort. However, every time we load and save our sample MIDI file, events get reversed. Here are program-changes that get reversed:

```
Save N: 0070: 6E 00 C4 48 00 C4 0C 00 C4 57 00 C4 19 00 C4 26 Save N+1: 0070: 6E 00 C4 26 00 C4 19 00 C4 57 00 C4 0C 00 C4 48
```

The 0070 is the offset within the versions of the b4uacuse-seq24.midi file.

Because of this mis-feature, and the very slow speed of loading a MIDI file when Sequencer64 is built for debugging, we are exploring using an std::mulitmap instead of an std::list. Search for occurrences of the SEQ64_USE_EVENT_MAP macro. (This actually works better than a list, for loading MIDI event, we have found, but may cause the upper limit of the number of playing sequences to drop a little, due to the overhead of incrementing multimap iterators versus list iterators).

Parameters

	rhs	The object to be compared against.
--	-----	------------------------------------

Returns

Returns true if the time-stamp and "rank" are less than those of the comparison object.

12.8.4.3 void seq64::event::set_timestamp(midipulse time) [inline]

Parameters

time	Provides the time value, in ticks, to set as the timestamp.
------	---

```
12.8.4.4 midipulse seq64::event::get_timestamp() const [inline]
```

12.8.4.5 midibyte seq64::event::get_channel()const [inline]

12.8.4.6 bool seq64::event::check_channel (int channel) const [inline]

Used in the SMF 0 track-splitting code.

Parameters

channel	The channel to check.
Unanio	THE CHAINCI TO CHECK.

Returns

Returns true if the given channel matches the event's channel.

```
12.8.4.7 static bool seq64::event::is_channel_msg( midibyte m) [inline], [static]
```

This function requires that the channel data have already been masked off.

Parameters

m The channel status or message byte to be tested, with the channel bits masked off.

We could add an optional boolean to cause the channel nybble to be explicitly cleared.

Returns

Returns true if the byte represents a MIDI channel message.

12.8.4.8 static bool seq64::event::is_one_byte_msg(midibyte m) [inline], [static]

The rest of the channel messages have two data bytes. This function requires that the channel data have already been masked off.

Parameters

m The channel status or message byte to be tested, with the channel bits masked off.

We could add an optional boolean to cause the channel nybble to be explicitly cleared.

Returns

Returns true if the byte represents a MIDI channel message that has only one data byte. However, if this function returns false, it might not be a channel message at all, so be careful.

12.8.4.9 static bool seq64::event::is_two_byte_msg (midibyte m) [inline], [static]

This function requires that the channel data have already been masked off.

Parameters

m The channel status or message byte to be tested, with the channel bits masked off.

We could add an optional boolean to cause the channel nybble to be explicitly cleared.

Returns

Returns true if the byte represents a MIDI channel message that has two data bytes. However, if this function returns false, it might not be a channel message at all, so be careful.

12.8.4.10 static bool seq64::event::is_note_msg(midibyte m) [inline], [static]

This function requires that the channel nybble has already been masked off.

Parameters

m The channel status or message byte to be tested, with the channel bits masked off.

We could add an optional boolean to cause the channel nybble to be explicitly cleared.

Returns

Returns true if the byte represents a MIDI note message.

12.8.4.11 static bool seq64::event::is_strict_note_msg(midibyte m) [inline], [static]

Parameters

m The channel status or message byte to be tested, with the channel bits masked off.

Returns

Returns true if the byte represents a MIDI note on/off message.

12.8.4.12 static bool seq64::event::is_desired_cc_or_not_cc(midibyte m, midibyte cc, midibyte datum) [inline], [static]

Note

The old logic was the first line, but can be simplified to the second line; the third line shows the abstract representation. Also made sure of this using a couple truth tables.

```
(m != EVENT_CONTROL_CHANGE) || (m == EVENT_CONTROL_CHANGE && d == cc)
    (m != EVENT_CONTROL_CHANGE) || (d == cc)
    a || (! a && b) => a || b

\param m
    The channel status or message byte to be tested, with the channel bits masked off.

\param cc
    The desired cc value, which the datum must match, if the message is a control-change message.

\param datum
    The current datum, to be compared to cc, if the message is a control-change message.

\return
    Returns true if the message is not a control-change, or if it is and the cc and datum parameters match.
```

12.8.4.13 void seq64::event::mod_timestamp(midipulse modtick) [inline]

Parameters

modtick The tick value to mod the timestamp against.

Returns

Returns a value ranging from 0 to _mod-1.

12.8.4.14 void seq64::event::set_status (midibyte status)

If a_status is a channel event, then the channel portion of the status is cleared using a bitwise AND against EVE← NT_CLEAR_CHAN_MASK.

Found in yet another fork of seq24:

// ORL fait de la merde

He also provided a very similar routine: set_status_midibus().

Stazed:

The record parameter, if true, does not clear channel portion on record for channel specific recording. The channel portion is cleared in sequence::stream_event() by calling set_status() (a_record = false) after the matching channel is determined. Otherwise, we use a bitwise AND to clear the channel portion of the status. All events will be stored without the channel nybble. This is necessary since the channel is appended by midibus::play() based on the track.

Instead of adding a "record" parameter to set_status(), we provide a more specific function, set_status_keep_channel(), for use in the mastermidibus class.

Parameters

status	The status byte, perhaps read from a MIDI file or edited in the sequencer's event editor. Sometime,
	this byte will have the channel nybble masked off. If that is the case, the eventcode/channel overload
	of this function is more appropriate.

12.8.4.15 void seq64::event::set_status (midibyte eventcode, midibyte channel)

Parameters

eventcode	The status byte, perhaps read from a MIDI file. This byte is assumed to have already had its low nybble cleared by masking against EVENT_CLEAR_CHAN_MASK.
channel	The channel byte. Combined with the event-code, this makes a valid MIDI "status" byte. This byte is assume to have already had its high nybble cleared by masking against EVENT GET CHAN MASK.

12.8.4.16 void seq64::event::set_status_keep_channel(midibyte eventcode) [inline]

It replaces stazed's set_status() with the optional "record" parameter.

Parameters

eventcode	The status byte, generally read from the MIDI buss.
-----------	---

12.8.4.17 void seq64::event::set_channel (midibyte channel) [inline]

It actually just sets the m_channel member. Note that the sequence channel generally overrides this value in the usage of the event.

Parameters

channel	The channel byte to be set.
---------	-----------------------------

```
12.8.4.18 midibyte seq64::event::get_status() const [inline]

12.8.4.19 void seq64::event::set_data(midibyte d1) [inline]
```

The second byte of data is zeroed. The data bytes are in a two =-byte array member, m_data.

Parameters

ĺ	d1	The byte value to set as the first data byte.
١	u,	ino byto value to bet do the mot data byto.

12.8.4.20 void seq64::event::set_data (midibyte d1, midibyte d2) [inline]

Parameters

d1	The first byte value to set.
d2	The second byte value to set.

12.8.4.21 void seq64::event::get_data (midibyte & d0, midibyte & d1) const [inline]

Parameters

	d0	[out] The return reference for the first byte.
ĺ	d1	[out] The return reference for the first byte.

```
12.8.4.22 void seq64::event::increment_data1() [inline]

12.8.4.23 void seq64::event::decrement_data1() [inline]

12.8.4.24 void seq64::event::increment_data2() [inline]

12.8.4.25 void seq64::event::decrement_data2() [inline]

12.8.4.26 bool seq64::event::append_sysex(midibyte * data, int dsize)
```

We now use a vector instead of an array, so there is no need for reallocation and copying of the current SYSEX data. The data represented by data and dsize is appended to that data buffer.

Parameters

data	Provides the additional SYSEX data. If not provided, nothing is done, and false is returned.
dsize	Provides the size of the additional SYSEX data. If not provided, nothing is done.

Returns

Returns false if there was an EVENT_MIDI_SYSEX_END byte in the appended data, or if an error occurred, and the caller needs to stop trying to process the data. We're not quite sure what to do with any extra data remains.

```
12.8.4.27 bool seq64::event::append_sysex ( midibyte data )
```

Parameters

```
data A single MIDI byte of data, assumed to be part of a SYSEX message event.
```

```
12.8.4.28 void seq64::event::restart_sysex()

(The m_sysex member used to be a pointer.)

12.8.4.29 SysexContainer& seq64::event::get_sysex() [inline]

12.8.4.30 const SysexContainer& seq64::event::get_sysex() const [inline]

12.8.4.31 void seq64::event::set_sysex_size(int len) [inline]

12.8.4.32 int seq64::event::get_sysex_size() const [inline]

12.8.4.33 void seq64::event::link(event * ev) [inline]
```

Parameters

ev Provides a pointer to the event value to set. If null, then m_has_link is set to false, to guarantee that is_linked() is correct.

```
12.8.4.34 event* seq64::event::get_linked() const [inline]

12.8.4.35 bool seq64::event::is_linked() const [inline]

12.8.4.36 void seq64::event::clear_link() [inline]

12.8.4.37 void seq64::event::paint() [inline]

12.8.4.38 void seq64::event::unpaint() [inline]

12.8.4.39 bool seq64::event::is_painted() const [inline]

12.8.4.40 void seq64::event::mark() [inline]
```

```
12.8.4.41 void seq64::event::unmark() [inline]
12.8.4.42 bool seq64::event::is_marked( ) const [inline]
12.8.4.43 void seq64::event::select() [inline]
12.8.4.44 void seq64::event::unselect() [inline]
12.8.4.45 bool seg64::event::is_selected() const [inline]
12.8.4.46 void seq64::event::make_clock( ) [inline]
12.8.4.47 midibyte seq64::event::data (int index ) const [inline]
12.8.4.48 midibyte seq64::event::get_note() const [inline]
12.8.4.49 void seq64::event::set_note ( midibyte note ) [inline]
Parameters
 note
         Provides the note value to set.
12.8.4.50 midibyte seq64::event::get_note_velocity() const [inline]
12.8.4.51 void seq64::event::set_note_velocity(int vel) [inline]
Parameters
       Provides the velocity value to set.
 vel
```

12.8.4.52 bool seq64::event::is_note_on() const [inline]

Currently assumes that the channel nybble has already been stripped.

Returns

Returns true if m status is EVENT NOTE ON.

12.8.4.53 bool seq64::event::is_note_off() const [inline]

Currently assumes that the channel nybble has already been stripped.

Returns

Returns true if m_status is EVENT_NOTE_OFF.

```
12.8.4.54 bool seq64::event::is_note() const [inline]
```

All of these are notes, associated with a MIDI key value. Uses the static function is_note_msg().

Returns

The return value of is_note_msg() is returned.

```
12.8.4.55 bool seq64::event::is_note_off_recorded() const [inline]
```

The channel nybble is masked off before the test.

Returns

Returns true if the event is a Note On event with velocity of 0.

```
12.8.4.56 void seq64::event::print ( ) const
```

```
12.8.4.57 int seq64::event::get_rank() const
```

The ranking, from high to low, is note off, note on, aftertouch, channel pressure, and pitch wheel, control change, and program changes.

note on/off, aftertouch, control change, etc.) The sort order is not determined by the actual status values.

The lower the ranking the more upfront an item comes in the sort order.

Returns

Returns the rank of the current m_status byte.

12.8.5 Field Documentation

```
12.8.5.1 midipulse seq64::event::m_timestamp [private]
```

```
12.8.5.2 midibyte seq64::event::m_status [private]
```

The channel is included when recording MIDI, but, once a sequence with a matching channel is found, the channel nybble is cleared for storage. The channel will be added back on the MIDI bus upon playback. The high nibble = type of event; The low nibble = channel. Bit 7 is present in all status bytes.

```
12.8.5.3 midibyte seq64::event::m_channel [private]
```

This member adds another 4 bytes to the event object, most likely.

```
12.8.5.4 midibyte seq64::event::m_data[SEQ64_MIDI_DATA_BYTE_COUNT] [private]
```

Remember that the most-significant bit of a data byte is always 0. A one-byte message uses only the 0th index.

```
12.8.5.5 SysexContainer seq64::event::m_sysex [private]
```

Adapted from Stazed's Seq32 project on GitHub.

```
12.8.5.6 int seq64::event::m_sysex_size [private]
```

Perhaps redundant.

```
12.8.5.7 event* seq64::event::m_linked [private]
```

```
12.8.5.8 bool seq64::event::m_has_link [private]
```

This item is used [via the get link() and link() accessors] in the sequence class.

```
12.8.5.9 bool seq64::event::m_selected [private]
12.8.5.10 bool seq64::event::m_marked [private]
```

12.8.5.11 bool seq64::event::m_painted [private]

12.9 seg64::event list::event key Class Reference

Provides a key value for an event map.

Public Member Functions

event_key (midipulse tstamp, int rank)

Principal event_key constructor.

event_key (const event &e)

Event-based constructor.

• bool operator< (const event_key &rhs) const

Provides the minimal operator needed to sort events using an event_key.

Private Attributes

• midipulse m_timestamp

The primary key-value for the key.

• int m rank

The sub-key-value for the key.

12.9.1 Detailed Description

Its types match the m_timestamp and get_rank() function of this event class.

12.9.2 Constructor & Destructor Documentation

12.9.2.1 seq64::event_list::event_key::event_key (midipulse tstamp, int rank)

Parameters

tstamp	The time-stamp is the primary part of the key. It is the most important key item.
rank	Rank is an arbitrary number used to prioritize events that have the same time-stamp. See the
	event::get_rank() function for more information.

12.9.2.2 seq64::event_list::event_key::event_key (const event & rhs)

This constructor makes it even easier to create an event_key. Note that the call to event::get_rank() makes a simple calculation based on the status of the event.

Parameters

rhs	Provides the event key to be copied.
-----	--------------------------------------

12.9.3 Member Function Documentation

12.9.3.1 bool seq64::event_list::event_key::operator< (const event_key & rhs) const

Parameters

Returns

Returns true if the rank and timestamp of the current object are less than those of rhs.

12.9.4 Field Documentation

12.9.4.1 midipulse seq64::event_list::event_key::m_timestamp [private]

12.9.4.2 int seq64::event_list::event_key::m_rank [private]

12.10 seq64::event_list Class Reference

The event_list class is a receptable for MIDI events.

Data Structures

class event_key

Provides a key value for an event map.

Public Member Functions

· event_list ()

Principal constructor.

event_list (const event_list &a_rhs)

Copy constructor.

event_list & operator= (const event_list &a_rhs)

Principal assignment operator.

∼event_list ()

A rote destructor.

· iterator begin ()

'Getter' function for member m_events.begin(), non-constant version.

• const_iterator begin () const

'Getter' function for member m_events.begin(), constant version.

· iterator end ()

'Getter' function for member m_events.end(), non-constant version.

· const_iterator end () const

'Getter' function for member m_events.end(), constant version.

· int count () const

Returns the number of events stored in m_events.

• bool empty () const

Returns true if there are no events.

bool add (const event &e)

Adds an event to the internal event list in an optionally sorted manner.

· bool is_modified () const

'Getter' function for member m_is_modified

• void unmodify ()

'Setter' function for member m_is_modified This function may be needed by some of the sequence editors.

· void remove (iterator ie)

Provides a wrapper for the iterator form of erase(), which is the only one that sequence uses.

• void clear ()

Provides a wrapper for clear().

void merge (event_list &el, bool presort=true)

Provides a merge operation for the event multimap analogous to the merge operation for the event list.

Static Public Member Functions

• static event & dref (iterator ie)

Wrapper for std::list::sort(), or, since multimaps are always sorted, an empty function.

static const event & dref (const_iterator ie)

Dereference const access for list or map.

Private Types

typedef std::multimap< event_key, event > Events

Types to use to swap between list and multimap implementations.

- typedef std::pair< event_key, event > EventsPair
- typedef std::multimap< event_key, event >::iterator iterator
- typedef std::multimap< event_key, event >::const_iterator const_iterator

Private Member Functions

• void link_new ()

Links a new event.

• void clear links ()

Clears all event links and unmarks them all.

• void verify_and_link (midipulse slength)

This function verifies state: all note-ons have an off, and it links note-offs with their note-ons.

bool mark_selected ()

Marks all selected events.

void mark_out_of_range (midipulse slength)

Marks all events that have a time-stamp that is out of range.

• void mark_all ()

Marks all events.

• void unmark_all ()

Unmarks all events.

• bool remove marked ()

Removes marked events.

void unpaint all ()

Unpaints all list-events.

• int count_selected_notes () const

Counts the selected note-on events in the event list.

• bool any_selected_notes () const

Indicates that at least one note is selected.

• int count_selected_events (midibyte status, midibyte cc) const

Counts the selected events, with the given status, in the event list.

• void select all ()

Selects all events, unconditionally.

void unselect_all ()

Deselects all events, unconditionally.

· void print () const

Prints a list of the currently-held events.

· const Events & events () const

'Getter' function for member m_events

Private Attributes

Events m_events

This list holds the current pattern/sequence events.

• bool m_is_modified

A new flag to indicate if an event was added or removed.

Friends

- · class editable_events
- · class midi container
- · class midi splitter
- class sequence

12.10.1 Detailed Description

Two implementations, an std::multimap, and the original, an std::list, are provided for comparison, and are selected at build time, by manually defining the SEQ64_USE_EVENT_MAP macro near the top of this module.

12.10.2 Member Typedef Documentation

```
12.10.2.1 typedef std::multimap<event_key, event> seq64::event_list::Events [private]
```

12.10.2.2 typedef std::pair<event key, event> seq64::event list::EventsPair [private]

12.10.2.3 typedef std::multimap<event_key, event>::iterator seq64::event_list::iterator [private]

12.10.3 Constructor & Destructor Documentation

```
12.10.3.1 seq64::event_list::event_list()
```

12.10.3.2 seq64::event_list::event_list (const event_list & rhs)

Parameters

	rhs	Provides the event list to be copied.
--	-----	---------------------------------------

```
12.10.3.3 seq64::event_list::~event_list()
```

12.10.4 Member Function Documentation

12.10.4.1 event_list & seq64::event_list::operator= (const event_list & rhs)

Follows the stock rules for such an operator, just assigning member values.

Parameters

rhs Provides the event list to be a

```
12.10.4.2 iterator seq64::event_list::begin() [inline]
```

12.10.4.3 const_iterator seq64::event_list::begin() const [inline]

12.10.4.4 iterator seq64::event_list::end() [inline]

```
12.10.4.5 const_iterator seq64::event_list::end() const [inline]

12.10.4.6 int seq64::event_list::count() const [inline]
```

We like returning an integer instead of size_t, and rename the function so nobody is fooled.

```
12.10.4.7 bool seq64::event_list::empty( ) const [inline]
return m_events.size() == 0;
```

It is a wrapper, wrapper for insert() or push_front(), with an option to call sort().

12.10.4.8 bool seq64::event_list::add (const event & e)

For the std::multimap implementation, This is an option if we want to make sure the insertion succeed.

If the std::list implementation has been built in, then the event list is sorted after the addition. This is a time-consuming operation.

Warning

This pushing (and, in writing the MIDI file, the popping), causes events with identical timestamps to be written in reverse order. Doesn't affect functionality, but it's puzzling until one understands what is happening. That's why we're now preferring to use a multimap as the container.

Parameters

e Provides the event to be added to the list.

Returns

Returns true if the insertion succeeded, as evidenced by an increment in container size.

```
12.10.4.9 bool seq64::event_list::is_modified() const [inline]

12.10.4.10 void seq64::event_list::unmodify() [inline]

But use it with great caution.

12.10.4.11 void seq64::event_list::remove(iterator ie) [inline]
```

Currently, no check on removal is performed. Set the modified-flag.

Parameters

ie Provides the iterator to the event to be removed.

12.10.4.12 void seq64::event_list::clear() [inline]

Set the modified-flag.

12.10.4.13 void seq64::event_list::merge (event_list & el, bool presort = true)

We have certain constraints to preserve, as the following discussion shows.

For std::list, sequence merges list T into list A by first calling T.sort(), and then A.merge(T). The merge() operation merges T into A by transferring all of its elements, at their respective ordered positions, into A. Both containers must already be ordered.

The merge effectively removes all the elements in T (which becomes empty), and inserts them into their ordered position within container (which expands in size by the number of elements transferred). The operation is performed without constructing nor destroying any element, whether T is an Ivalue or an rvalue, or whether the value-type supports move-construction or not.

Each element of T is inserted at the position that corresponds to its value according to the strict weak ordering defined by operator <. The resulting order of equivalent elements is stable (i.e. equivalent elements preserve the relative order they had before the call, and existing elements precede those equivalent inserted from x). The function does nothing if (&x == this).

For std::multimap, sorting is automatic. However, unless move-construction is supported, merging will be less efficient than for the list version. Also, we need a way to include duplicates of each event, so we need to use a multimap. Once all this setup, merging is really just insertion. And, since sorting isn't needed, the multimap actually turns out to be faster.

Parameters

el	Provides the event list to be merged into the current event list.
'	If true, the events are presorted. This is a requirement for merging an std::list, but is a no-op for the std::multimap implementation.

12.10.4.14 static event& seq64::event_list::dref(iterator ie) [inline], [static]

Dereference access for list or map.

Parameters

ie Provides the iterator to the event to which to get a reference.

12.10.4.15 static const event& seq64::event_list::dref (const_iterator ie) [inline], [static]

Parameters

ie Provides the iterator to the event to which to get a reference.

```
12.10.4.16 void seq64::event_list::link_new( ) [private]
```

This function checks for a note on, then look for its note off. This function is provided in the event_list because it does not depend on any external data. Also note that any desired thread-safety must be provided by the caller.

```
12.10.4.17 void seq64::event_list::clear_links( ) [private]
```

12.10.4.18 void seq64::event_list::verify_and_link(midipulse slength) [private]

Not threadsafe

Parameters

slenath	Provides the length beyond which events will be pruned.

```
12.10.4.19 bool seq64::event_list::mark_selected() [private]
```

Returns

Returns true if there was even one event selected and marked.

```
12.10.4.20 void seq64::event_list::mark_out_of_range( midipulse slength ) [private]
```

Used for killing (pruning) those events not in range. If the current time-stamp is greater than the length, then the event is marked for pruning.

Note

This code was comparing the timestamp as greater than or equal to the sequence length. However, being equal is fine. This may explain why the midifile code would add one tick to the length of the last note when processing the end-of-track.

Parameters

_		
	slength	Provides the length beyond which events will be pruned.

```
12.10.4.21 void seq64::event_list::mark_all( ) [private]
```

Not yet used, but might come in handy with the event editor dialog.

```
12.10.4.22 void seq64::event_list::unmark_all( ) [private]
```

```
12.10.4.23 bool seq64::event_list::remove_marked() [private]
```

Note how this function handles removing a value to avoid incrementing a now-invalid iterator.

Threadsafe

Returns

Returns true if at least one event was removed.

```
12.10.4.24 void seq64::event_list::unpaint_all() [private]

12.10.4.25 int seq64::event_list::count_selected_notes() const [private]

12.10.4.26 bool seq64::event_list::any_selected_notes() const [private]
```

Acts like event_list::count_selected_notes(), but stops after finding a selected note. We could add a flag to count
__selected_notes() to break, I suppose.

Returns

Returns true if at least one note is selected.

12.10.4.27 int seq64::event_list::count_selected_events (midibyte status, midibyte cc) const [private]

If the event is a control change (CC), then it must also match the given CC value.

Parameters

status	The desired status value to count.
CC	The desired control-change to count. Used only if the status parameter indicates a control-change event.

Returns

Returns the number of selected events.

```
12.10.4.28 void seq64::event_list::select_all() [private]

12.10.4.29 void seq64::event_list::unselect_all() [private]

12.10.4.30 void seq64::event_list::print() const [private]

12.10.4.31 const Events& seq64::event_list::events() const [inline], [private]

12.10.5 Friends And Related Function Documentation

12.10.5.1 friend class editable_events [friend]
```


12.10.5.3	<pre>friend class midi_splitter [friend]</pre>
12.10.5.4	<pre>friend class sequence [friend]</pre>
12.10.6	Field Documentation
12.10.6.1	Events seq64::event_list::m_events [private]
12.10.6.2	<pre>bool seq64::event_list::m_is_modified [private]</pre>
We may eventedit	need to give client code a way to reload the sequence. This is currently an issue when a seqroll and an /eventslots are active for the same sequence.
12.11	seq64::eventedit Class Reference

This class supports an Event Editor that is used to tweak the details of events and get a better idea of the mix of

Generated by Doxygen

events in a sequence.

Inheritance diagram for seq64::eventedit:



Public Member Functions

• eventedit (perform &p, sequence &seq)

Principal constructor, has a reference to a perform object.

virtual ∼eventedit ()

This rote constructor does nothing.

Private Member Functions

void enqueue_draw ()

Helper wrapper for calling eventslots::queue_draw().

void set_seq_title (const std::string &title)

Sets m_label_seq_name to the title.

void set_seq_time_sig (const std::string &sig)

Sets m_label_time_sig to the time-signature string.

• void set_seq_ppqn (const std::string &p)

Sets m_label_ppqn to the parts-per-quarter-note string.

void set_seq_count ()

Sets m label ev count to the number-of-events string.

void set_event_category (const std::string &c)

Sets m_label_category to the category string.

void set_event_timestamp (const std::string &ts)

Sets m entry ev timestamp to the time-stamp string.

void set_event_name (const std::string &n)

Sets m_entry_ev_name to the name-of-event string.

• void set_event_data_0 (const std::string &d)

Sets m_entry_ev_data_0 to the first data byte string.

void set_event_data_1 (const std::string &d)

Sets m_entry_data_1 to the second data byte string.

void perf modify ()

Provides a way to mark the perform object as modified, when the modified sequence is saved.

• void set_dirty (bool flag=true)

Sets the "modified" status of the user-interface.

void v adjustment (int value)

Sets the parameters for the vertical scroll-bar, using only the value parameter.

void v_adjustment (int value, int lower, int upper)

Sets the parameters for the vertical scroll-bar that is associated with the eventslots event-list user-interface.

void change focus (bool set it=true)

Changes what perform and mainwid see as the "current sequence".

void close_out ()

Handles closing the sequence editor, common code for handle_cancel() and handle_close().

• void handle close ()

Handles closing the sequence editor.

void handle_delete ()

Initiates the deletion of the current editable event.

void handle_insert ()

Initiates the insertion of a new editable event.

· void handle modify ()

Passes the edited fields to the current editable event in the eventslot.

void handle_save ()

Handles saving the edited data back to the original sequence.

• void handle cancel ()

Cancels the edits and closes the dialog box.

void on_realize ()

This callback function calls the base-class on_realize() function.

void on set focus (Widget *focus)

On receiving focus, attempt to tell mainwid that this sequence is now the current sequence.

• bool on_focus_in_event (GdkEventFocus *)

Implements the on-focus event handling.

bool on_focus_out_event (GdkEventFocus *)

Implements the on-unfocus event handling.

bool on_key_press_event (GdkEventKey *ev)

This function is the callback for a key-press event.

bool on_delete_event (GdkEventAny *event)

Handles an on-delete event.

Private Attributes

• Gtk::Table * m table

A whole horde of GUI elements.

Gtk::Adjustment * m_vadjust

Vertical paging for event list.

• Gtk::VScrollbar * m vscroll

Vertical scroll for event list.

• eventslots * m eventslots

Drawing area for events.

• Gtk::HBox * m htopbox

Padding at the top of the dialog.

• Gtk::VBox * m_showbox

Area for sequence information.

• Gtk::VBox * m editbox

Text-edits and buttons for data.

• Gtk::VBox * m_optsbox

Reserved for future options.

• Gtk::HBox * m_bottbox

Holds the Save and Close buttons.

• Gtk::VBox * m_rightbox

Used for padding on right side.

• Gtk::Button * m_button_del

"Delete Current Event (*)" button.

• Gtk::Button * m_button_ins

"Insert New Event" button.

• Gtk::Button * m_button_modify

"Modify New Event" button.

• Gtk::Button * m_button_save

"Save to Sequence" button.

• Gtk::Button * m_button_cancel

"Close" button.

• Gtk::Label * m_label_seq_name

Items for the inside of the m_showbox member.

• Gtk::Label * m_label_time_sig

Shows time signature for pattern.

• Gtk::Label * m_label_ppqn

Shows the parts per quarter note.

Gtk::Label * m label channel

Shows channel number of pattern.

• Gtk::Label * m_label_ev_count

Shows the count of pattern events.

```
    Gtk::Label * m_label_spacer
```

Spacer for the showbox elements.

• Gtk::Label * m_label_modified

Shows "[Modified]" if edited.

• Gtk::Label * m_label_category

Items for the inside of the m_editbox member.

Gtk::Entry * m_entry_ev_timestamp

Text edit for event time-stamp.

• Gtk::Entry * m_entry_ev_name

Text edit for MIDI event name.

• Gtk::Entry * m_entry_ev_data_0

Text edit for first event datum.

• Gtk::Entry * m_entry_ev_data_1

Text edit for second event datum.

Gtk::Label * m_label_time_fmt

Optsbox item, only "Sequencer64".

• Gtk::Label * m_label_right

Padding at the right of dialog.

• sequence & m_seq

A reference to the sequence being edited, to control its editing flag.

• bool m_have_focus

Indicates that the focus has already been changed to this sequence.

Friends

· class eventslots

Additional Inherited Members

12.11.1 Constructor & Destructor Documentation

```
12.11.1.1 seq64::eventedit::eventedit ( perform & p, sequence & seq )
```

We've reordered the pointer members and put them in the initializer list to make the constructor a bit cleaner.

Adjustment parameters:

```
value initial value lower minimum value upper maximum value step_increment step increment page_increment page_size page size
```

Table constructor parameters:


rows columns homogenous Table attach() parameters:

```
child widget to add.

left_attach column number to attach left side of a child widget right_attach column number to attach right side of a child widget top_attach row number to attach the top of a child widget bottom_attach row number to attach the bottom of a child widget xoptions properties of the child widget when table resized yoptions same as xoptions, except vertical.

xpadding padding on L and R of widget added to table ypadding amount of padding above and below the child widget
```

Layout:



Parameters

р	Refers to the main performance object.
seq	Refers to the sequence holding the event data to be edited.

The sequence dirty flags, and this allows the sequence's pattern slot to be updated, which, for example, allows the new experimental in-edit-highlight feature to work. To get the eventedit to also show the in-edit highlighting, we can make the sequence::set_dirty_mp() call. This call does not cause a prompt for saving the file when exiting.

```
12.11.1.2 seq64::eventedit::~eventedit() [virtual]
```

We're going to have to run the application through valgrind to make sure that nothing is left behind.

12.11.2 Member Function Documentation

```
12.11.2.1 void seq64::eventedit::enqueue_draw( ) [private]
```

12.11.2.2 void seq64::eventedit::set_seq_title(const std::string & title) [private]

title The name of the sequence.

12.11.2.3 void seq64::eventedit::set_seq_time_sig(const std::string & sig) [private]

Parameters

sig The time signature of the sequence.

12.11.2.4 void seq64::eventedit::set_seq_ppqn (const std::string & p) [private]

Parameters

p The parts-per-quarter-note string for the sequence.

12.11.2.5 void seq64::eventedit::set_seq_count() [private]

12.11.2.6 void seq64::eventedit::set_event_category(const std::string & c) [private]

Parameters

c The category string for the current event.

12.11.2.7 void seq64::eventedit::set_event_timestamp(const std::string & ts) [private]

Parameters

ts The time-stamp string for the current event.

12.11.2.8 void seq64::eventedit::set_event_name(const std::string & n) [private]

Parameters

n The name-of-event string for the current event.

12.11.2.9 void seq64::eventedit::set_event_data_0 (const std::string & d) [private]

Parameters

d The first data byte string for the current event.

12.11.2.10 void seq64::eventedit::set_event_data_1 (const std::string & d) [private]

d The second data byte string for the current event.

```
12.11.2.11 void seq64::eventedit::perf_modify( ) [private]
```

12.11.2.12 void seq64::eventedit::set_dirty(bool flag = true) [private]

This includes changing a label and enabling/disabling the Save button.

Parameters

12.11.2.13 void seq64::eventedit::v_adjustment(int value) [private]

This function overload provides a common use case.

Parameters

	value	The new current value to be indicated by the scroll-bar.	
--	-------	--	--

12.11.2.14 void seq64::eventedit::v_adjustment(int value, int lower, int upper) [private]

It keeps the frame scroll-bar in sync with the frame movement actions. Some of the parameters are obtained from the eventslots object:

- Page size comes from eventslots::line_maximum().
- Page increment is a little less than the page-size value.

Parameters

value	The current value to be indicated by the scroll-bar. It will lie between the lower and upper parameter.
lower	The lowest value to be indicated by the scroll-bar.
upper	The highest value to be indicated by the scroll-bar.

12.11.2.15 void seq64::eventedit::change_focus (bool set_it = true) [private]

Similar to the same function in seqedit.

Parameters

set⊷	If true (the default value), indicates we want focus, otherwise we want to give up focus.
_it	

```
12.11.2.16 void seq64::eventedit::close_out() [private]
12.11.2.17 void seq64::eventedit::handle_close() [private]
Simply calls close_out().

12.11.2.18 void seq64::eventedit::handle_delete() [private]
12.11.2.19 void seq64::eventedit::handle_insert() [private]
```

The event's location will be determined by the timestamp and existing events. Note that we have to recalibrate the scroll-bar when we insert/delete events by calling v_adjustment().

```
12.11.2.20 void seq64::eventedit::handle_modify() [private]
```

Note that there are two cases to worry about. If the timestamp has not changed, then we can simply modify the existing current event in place. Otherwise, we need to delete the old event and insert the new one. But that is done for us by eventslots::modify_current_event().

```
12.11.2.21 void seq64::eventedit::handle_save() [private]
```

The event list in the original sequence is cleared, and the editable events are converted to plain events, and added to the container, one by one.

Todo Could also support writing the events to a new sequence, for added flexibility.

```
12.11.2.22 void seq64::eventedit::handle_cancel( ) [private]
```

In order for removing the current-highlighting in the mainwd or perfedit windows, some of the work of handle_close() needs to be done here as well.

```
12.11.2.23 void seq64::eventedit::on_realize( ) [private]
```

Then it sets the vertical adjustment to account for the number of events in the eventslot.

```
12.11.2.24 void seq64::eventedit::on_set_focus ( Widget * focus ) [private]
```

Only works in certain circumstances.

Parameters

focus The widget that has the focus. Merely passed on to gui_window_gtk2's version of this function.

```
12.11.2.25 bool seq64::eventedit::on_focus_in_event ( GdkEventFocus * ) [private]
```

It sets the focus flag and calls change focus().

```
12.11.2.26 bool seq64::eventedit::on_focus_out_event( GdkEventFocus * ) [private]
```

It resets the focus flag and calls change_focus().

```
12.11.2.27 bool seq64::eventedit::on_key_press_event ( GdkEventKey * ev ) [private]
```

If the Up or Down arrow is pressed (later, k and j :-), then we tell the eventslots object to move the "current event" highlighting up or down. In Gtkmm, these arrows also cause movement from one edit field to the next, so we disable that process if the event was handled here.

Note that some vi-like keys were supported, but they are needed for the edit fields, so cannot be used here. Also, the Delete key is needed for the edit fields. For now, we replace it with the asterisk, which is easy to access from the numeric pad of a keyboard, and allows for rapid deletion. The Insert key also causes confusing effects in the edit fields, so we replace it by the slash. Note that the asterisk and slash should not be required in any of the edit fields.

HOWEVER, "/" still gets passed the edit fields (!), so you'll just have to click the button to insert an event. Let's try the backslash!

Parameters

```
ev The key event to process.
```

Returns

Returns true if the event got handled somewhere along the line.

```
12.11.2.28 bool seq64::eventedit::on_delete_event ( GdkEventAny * event ) [private]
```

It sets the sequence object's editing flag to false, and deletes "this". This function is called if the "Close" ("X") button in the window's title bar is clicked. That is a different action from clicking the Close button.

Returns

Always returns false.

12.11.3 Friends And Related Function Documentation

```
12.11.3.1 friend class eventslots [friend]
```

12.11.4 Field Documentation

```
12.11.4.1 Gtk::Table* seq64::eventedit::m_table [private]
```

Provides the layout table for UI.

```
12.11.4.2 Gtk::Adjustment* seq64::eventedit::m_vadjust [private]
12.11.4.3 Gtk::VScrollbar* seq64::eventedit::m_vscroll [private]
12.11.4.4 eventslots* seq64::eventedit::m_eventslots [private]
12.11.4.5 Gtk::HBox* seq64::eventedit::m_htopbox [private]
12.11.4.6 Gtk::VBox* seq64::eventedit::m_showbox [private]
12.11.4.7 Gtk::VBox* seq64::eventedit::m_editbox [private]
12.11.4.8 Gtk::VBox* seq64::eventedit::m_optsbox [private]
12.11.4.9 Gtk::HBox* seq64::eventedit::m_bottbox [private]
12.11.4.10 Gtk::VBox* seq64::eventedit::m_rightbox [private]
12.11.4.11 Gtk::Button* seq64::eventedit::m_button_del [private]
12.11.4.12 Gtk::Button* seq64::eventedit::m_button_ins [private]
12.11.4.13 Gtk::Button* seq64::eventedit::m_button_modify [private]
12.11.4.14 Gtk::Button* seq64::eventedit::m_button_save [private]
12.11.4.15 Gtk::Button* seq64::eventedit::m_button_cancel [private]
12.11.4.16 Gtk::Label* seq64::eventedit::m_label_seq_name [private]
Shows the name of the pattern.
12.11.4.17 Gtk::Label* seq64::eventedit::m_label_time_sig [private]
12.11.4.18 Gtk::Label* seq64::eventedit::m_label_ppqn [private]
12.11.4.19 Gtk::Label* seq64::eventedit::m_label_channel [private]
12.11.4.20 Gtk::Label* seq64::eventedit::m_label_ev_count [private]
12.11.4.21 Gtk::Label* seq64::eventedit::m_label_spacer [private]
12.11.4.22 Gtk::Label* seq64::eventedit::m_label_modified [private]
12.11.4.23 Gtk::Label* seq64::eventedit::m_label_category [private]
Shows the type of MIDI event.
```

```
12.11.4.24 Gtk::Entry* seq64::eventedit::m_entry_ev_timestamp [private]
12.11.4.25 Gtk::Entry* seq64::eventedit::m_entry_ev_name [private]
12.11.4.26 Gtk::Entry* seq64::eventedit::m_entry_ev_data_0 [private]
12.11.4.27 Gtk::Entry* seq64::eventedit::m_entry_ev_data_1 [private]
12.11.4.28 Gtk::Label* seq64::eventedit::m_label_time_fmt [private]
12.11.4.29 Gtk::Label* seq64::eventedit::m_label_right [private]
12.11.4.30 sequence& seq64::eventedit::m_seq [private]
12.11.4.31 bool seq64::eventedit::m_have_focus [private]
```

This item is to modify the mainwid and perfedit "edit-sequence" value in order to highlight pattern slot of the pattern/event editor that currently has the user-input focus.

12.12 seq64::eventslots Class Reference

This class implements the left-side list of events in the pattern event-edit window.

Inheritance diagram for seq64::eventslots:

```
seq64::gui_palette_gtk2
seq64::gui_drawingarea_gtk2
             ea_init()
```

Public Member Functions

- eventslots (perform &p, eventedit &parent, sequence &seq, Gtk::Adjustment &vadjust)

 Principal constructor for this user-interface object.
- virtual \sim eventslots ()

Let's provide a do-nothing virtual destructor.

• int event_count () const

'Getter' function for member m_event_count Returns the number of total events in the sequence represented by the eventslots object.

int line_count () const

'Getter' function for member m_line_count Returns the current number of rows (events) in the eventslots's display.

• int line maximum () const

'Getter' function for member m_line_maximum Returns the maximum number of rows (events) in the eventslots's display.

· int line increment () const

Provides the "page increment" or "line increment" of the frame, This value is the current line-maximum of the frame minus its overlap value.

int top_index () const

'Getter' function for member m_top_index

• int current_index () const

'Getter' function for member m current index

int pager_index () const

'Getter' function for member m_pager_index

Private Member Functions

· bool load_events ()

Grabs the event list from the sequence and uses it to fill the editable-event list.

void set_current_event (const editable_events::iterator ei, int index, bool full_redraw=true)

Set the current event, which is the event that is highlighted.

bool insert_event (const editable_event &edev)

Inserts an event.

 bool insert_event (const std::string &evtimestamp, const std::string &evname, const std::string &evdata0, const std::string &evdata1)

Inserts an event based on the setting provided, which the eventedit object gets from its Entry fields.

• bool delete_current_event ()

Deletes the current event, and makes adjustments due to that deletion.

• bool modify_current_event (const std::string &evtimestamp, const std::string &evname, const std::string &evdata0, const std::string &evdata1)

Modifies the data in the currently-selected event.

• bool save_events ()

Writes the events back to the sequence.

void select_event (int event_index=SEQ64_NULL_EVENT_INDEX, bool full_redraw=true)

Selects and highlights the event that is located in the frame at the given event index.

 void set_text (const std::string &evcategory, const std::string &evtimestamp, const std::string &evname, const std::string &evdata0, const std::string &evdata1)

Sets the text in the parent dialog, eventedit.

• void enqueue_draw ()

Wraps queue_draw().

int convert_y (int y)

Converts a y-value into an event index relative to 0 (the top of the eventslots window/pixmap) and returns it.

• void draw event (editable events::iterator ei, int index)

Draw the given slot/event.

void draw_events ()

Draws all of the events in the current eventslots frame.

· void change vert ()

Change the vertical offset of events.

void page_movement (int new_value)

Adjusts the vertical position of the frame according to the given new scrollbar/vadjust value.

void page_topper (editable_events::iterator newcurrent)

Adjusts the vertical position of the frame according to the given new bottom iterator.

int decrement_top ()

Decrements the top iterator, if possible.

int increment_top ()

Increments the top iterator, if possible.

int decrement_current ()

Decrements the current iterator, if possible.

int increment_current ()

Increments the current iterator, if possible.

• int decrement_bottom ()

Decrements the bottom iterator, if possible.

int increment_bottom ()

Increments the bottom iterator, if possible.

• void on_realize ()

Handles the callback when the window is realized.

bool on_expose_event (GdkEventExpose *ev)

Handles an on-expose event.

bool on_button_press_event (GdkEventButton *ev)

Provides the callback for a button press, and it handles only a left mouse button.

• bool on_button_release_event (GdkEventButton *ev)

Handles a button-release for the right button, bringing up a popup menu.

• bool on focus in event (GdkEventFocus *ev)

This callback is an attempt to get keyboard focus into the eventslots pixmap area.

bool on focus out event (GdkEventFocus *ev)

This callback handles an out-of-focus event by resetting the flag HAS_FOCUS.

• bool on scroll event (GdkEventScroll *ev)

Handle the scrolling of the window.

• void on_size_allocate (Gtk::Allocation &)

Handles a size-allocation event.

void on_move_up ()

Move to the previous event.

void on_move_down ()

Move to the next event.

void on_frame_up ()

Move to the previous frame.

• void on frame down ()

Move to the next frame.

• void on frame home ()

Move to the first frame.

void on_frame_end ()

Move to the last frame.

Private Attributes

· eventedit & m_parent

Provides a link to the eventedit that created this object.

sequence & m_seq

Provides a reference to the sequence that this dialog is meant to view or modify.

• editable_events m_event_container

Holds the editable events for this sequence.

· int m slots chars

Provides the number of the characters in the name box.

· int m char w

Provides the "real" width of a character.

• int m_setbox_w

Provides the width of the "set number" box.

int m_slots_x

Provides the width of the names box, which is the width of a character for 24 characters.

int m_slots_y

Provides the height of the names box, which is hardwired to 24 pixels.

int m_event_count

The current number of events in the edited container.

int m_line_count

Counts the number of displayed events, which depends on how many events there are (m_event_count) and the size of the event list (m_line_maximum).

· int m line maximum

Counts the maximum number of displayed events, which depends on the size of the event list (and thus the size of the dialog box for the event editor).

· int m line overlap

Provides a little overlap for paging through the frame.

int m_top_index

The index of the event that is 0th in the visible list of events.

• int m_current_index

Indicates the index of the current event within the frame.

editable_events::iterator m_top_iterator

Provides the top "pointer" to the start of the editable-events section that is being shown in the user-interface.

• editable_events::iterator m_bottom_iterator

Provides the bottom "pointer" to the end of the editable-events section that is being shown in the user-interface.

• editable_events::iterator m_current_iterator

Provides the "pointer" to the event currently in focus.

• int m_pager_index

Indicates the event index that matches the index value of the vertical pager.

Friends

· class eventedit

Additional Inherited Members

12.12.1 Constructor & Destructor Documentation

12.12.1.1 seq64::eventslots::eventslots (perform & p, eventedit & parent, sequence & seq, Gtk::Adjustment & vadjust)

```
12.12.1.2 virtual seq64::eventslots::~eventslots() [inline], [virtual]
```

12.12.2 Member Function Documentation

```
12.12.2.1 int seq64::eventslots::event_count() const [inline]
```

```
12.12.2.2 int seq64::eventslots::line_count() const [inline]
```

12.12.2.3 int seq64::eventslots::line_maximum() const [inline]

12.12.2.4 int seq64::eventslots::line_increment() const [inline]

12.12.2.5 int seq64::eventslots::top_index() const [inline]

12.12.2.6 int seq64::eventslots::current_index() const [inline]

12.12.2.7 int seq64::eventslots::pager_index() const [inline]

12.12.2.8 bool seq64::eventslots::load_events() [private]

Determines how many events can be shown in the GUI [later] and adjusts the top and bottom editable-event iterators to show the first page of events.

Returns

Returns true if the event iterators were able to be set up as valid.

12.12.2.9 void seq64::eventslots::set_current_event (const editable_events::iterator ei, int index, bool full_redraw = true) [private]

Note in the snprintf() calls that the first digit is part of the data byte, so that translation is easier.

Parameters

ei	The iterator that points to the event.
index	The index (re 0) of the event, starting at the top line of the frame. It is a frame index, not a container index.
full_redraw	If true (the default) does a full redraw of the frame. Otherwise, only the current event is drawn. Generally, the only time a single event (actually, two adjacent events) is convenient to draw is when using the arrow keys, where the speed of keystroke auto-repeats makes the full-frame update scrolling very flickery and disconcerting.

12.12.2.10 bool seq64::eventslots::insert_event (const editable_event & edev) [private]

What actually happens here depends if the new event is before the frame, within the frame, or after the frame, based on the timestamp.

If before the frame: To keep the previous events visible, we do not need to increment the iterators (insertion does not affect multimap iterators), but we do need to increment their indices. The contents shown in the frame should not change.

If at the frame top: The new timestamp equals the top timestamp. We don't know exactly where the new event goes in the multimap, but we do have an new event.

If at the frame bottom: TODO

If after the frame: No action needed if the bottom event is actually at the bottom of the frame. But if the frame is not yet filled, we need to increment the bottom iterator, and its index.

Note

Actually, it is far easier to just adjust all the counts and iterators and redraw the screen, as done by the page_topper() function.

Parameters

edev	The event to insert, prebuilt.
------	--------------------------------

Returns

Returns true if the event was inserted.

12.12.2.11 bool seq64::eventslots::insert_event (const std::string & evtimestamp, const std::string & evname, const std::string & evdata0, const std::string & evdata1) [private]

It calls the other insert event() overload.

Note that we need to qualify the temporary event class object we create below, with the seq64 namespace, otherwise the compiler thinks we're trying to access some Gtkmm thing.

Parameters

evtimestamp	The time-stamp of the new event, as obtained from the event-edit timestamp field.	
evname The type name (status name) of the new event, as obtained from the event-edit event-		
	field.	
evdata0	The first data byte of the new event, as obtained from the event-edit data 1 field.	
evdata1	The second data byte of the new event, as obtained from the event-edit data 2 field. Used only for two-parameter events.	

Returns

Returns true if the event was inserted.

```
12.12.2.12 bool seq64::eventslots::delete_current_event( ) [private]
```

To delete the current event, this function moves the current iterator to the next event, deletes the previously-current iterator, adjusts the event count and the bottom iterator, and redraws the pixmap. The exact changes depend upon whether the deleted event was at the top of the visible frame, within the visible frame, or at the bottom the visible frame. Note that only visible events can be the current event, and thus get deleted.

Basically, when an event is deleted, the frame (delimited by the event-index members) stays in place, while the frame iterators move to the previous event. If the top of the frame would move to before the first event, then the frame must shrink.

Top case: If the current iterator is the top (of the frame) iterator, then the top iterator needs to be incremented. The new top event has the same index as the now-gone top event. The index of the bottom event is decremented, since an event before it is now gone. The bottom iterator moves to the next event, which is now at the bottom of the frame. The current event is treated like the top event.

Inside case: If the current iterator is in the middle of the frame, the top iterator and index remain unchanged. The current iterator is incremented, but its index is now the same as the old bottom index. Same for the bottom iterator

Bottom case: If the current iterator (and bottom iterator) point to the last event in the frame, then both of them need to be decremented. The frame needs to be moved up by one event, so that the current event remains at the bottom (it's just simpler to manage that way).

If there is no event after the bottom of the frame, the iterators that now point to end() must backtrack one event. If the container becomes empty, then everything is invalidated.

Returns

Returns true if the delete was possible. If the container was empty or became empty, then false is returned.

12.12.2.13 bool seq64::eventslots::modify_current_event (const std::string & evtimestamp, const std::string & evname, const std::string & evdata0, const std::string & evdata1) [private]

If the timestamp has changed, however, we can't just modify the event in place. Instead, we finish modifying the event, but tell the caller to delete and reinsert the new event (in its proper new location based on timestamp).

This function always copies the original event, modifiles the copy, deletes the original event, and inserts the "new" event into the editable-event container.

evtimestamp	Provides the new event time-stamp as edited by the user.
evname	Provides the event name as edited by the user.
evdata0	Provides the first data byte as edited by the user.
evdata1	Provides the second data byte as edited by the user.

Returns

Returns true simply if the event-count is greater than 0.

```
12.12.2.14 bool seq64::eventslots::save_events( ) [private]
```

Also sets the dirty flag for the sequence, via the sequence::add_event() function, but this doesn't seem to set the perform dirty flag. So now we pass the modification buck to the parent, who passes it to the perform object.

We added a copy_events() function in the sequence class to replace add_event() for the purpose of reconstructing the events container for the sequence. It is locked by a mutex, and so will not draw until all is done, preventing a nasty segfault (all segfaults are nasty).

We create a new plain event container here, and then passing it to the new locked/threadsafe sequence::copy_
events() function that clears the sequence container and copies the events from the parameter container.

Note that this code will operate event if all events were deleted.

Returns

Returns true if the operations succeeded.

```
12.12.2.15 void seq64::eventslots::select_event ( int event_index = SEQ64_NULL_EVENT_INDEX, bool full_redraw = true ) [private]
```

The event index is provided by converting the y-coordinate of the mouse pointer into a slot number, and then an event index (actually the slot-distance from the m top iterator. Confusing, yes no?

Note that, if the event index is negative, then we just queue up a draw operation, which should paint an empty frame – the event container is empty.

Parameters

event_index	Provides the numeric index of the event in the event frame, or SEQ64_NULL_EVENT if there is	1
	no event to draw.	
full_redraw	Defaulting to true, this parameter can be set to false in some case to reduce the flickering of the	
	frame under fast movement.	

12.12.2.16 void seq64::eventslots::set_text (const std::string & evcategory, const std::string & evtimestamp, const std::string & evdata0, const std::string & evdata1) [private]

evcategory	The category of event to be set in the parent.
evtimestamp	The event time-stamp to be set in the parent.
evname	The event name to be set in the parent.
evdata0	The first event data byte to be set in the parent.
evdata1	The second event data byte to be set in the parent.

```
12.12.2.17 void seq64::eventslots::enqueue_draw( ) [private]
```

```
12.12.2.18 int seq64::eventslots::convert_y ( int y ) [private]
```

Parameters

Returns

Returns the index of the event position in the user-interface, which should range from 0 to m_line_count.

```
12.12.2.19 void seq64::eventslots::draw_event ( editable_events::iterator ei, int index ) [private]
```

The slot contains the event details in (so far) one line of text in the box:

```
| timestamp | event kind | channel | data 0 name + value | data 1 name + value
```

Currently, this view shows only events that get copied to the sequence's event list. This rules out the following items from the view:

```
MThd (song header)
```

- MTrk and Meta TrkEnd (track marker, a sequence has only one track)
- SeqNr (sequence number)
- SeqSpec (but there are three that might appear, see below)
- Meta TrkName

The events that are shown in this view are:

```
One-data-value events:
```

- Program Change
- Channel Pressure
- Two-data-value events:
 - Note Off
 - Note On
 - Aftertouch
 - Control Change
 - Pitch Wheel
- Other:
 - SysEx events, with partial show of data bytes
 - SeqSpec events (TBD):
 - Key
 - Scale
 - Background sequence

The index of the event is shown in the editor portion of the eventedit dialog.

```
12.12.2.20 void seq64::eventslots::draw_events() [private]
```

It first clears the whole bitmap to white, so that no artifacts from the previous state of the frame are left behind.

Need to figure out how to calculate the number of displayable events.

```
m_line_maximum = ???

12.12.2.21 void seq64::eventslots::change_vert( ) [private]
```

Note that m_vadjust is the Gtk::Adjustment object that the eventedit parent passes to the gui_drawingarea_gtk2 constructor.

The top-event and bottom-event indices (and their corresponding editable-event iterators) delimit the part of the event container that is displayed in the eventslots user-interface. The top-event index starts at 0, and the bottom-event is larger (initially, by 42 slots).

When the scroll-bar thumb moves up or down, we need to change both event indices and both event iterators by the corresponding amount. Luckily, the std::multimap iterator is bidirectional.

Note that we may need to reduce the movement of events to a value less than a page; it can be limited backwards by the value of the top index, and forward by the value of the bottom index.

```
12.12.2.22 void seq64::eventslots::page_movement(int new_value) [private]
```

The adjustment is done via movement from the current position.

Do we even need a way to detect excess movement? The scrollbar, if properly set up, should never move the frame too high or too low. Verified by testing.

Parameters

new_value	Provides the new value of the scrollbar position.
-----------	---

```
12.12.2.23 void seq64::eventslots::page_topper( editable events::iterator newcurrent ) [private]
```

The adjustment is done "from scratch". We've found page movement to be an insoluable problem in some editing circumstances. So now we move to the inserted event, and make it the top event.

However, always moving an inserted event to the top is a bit annoying. So now we backtrack so that the inserted event is at the bottom.

Parameters

12.12.2.24 int seq64::eventslots::decrement_top() [private]

Returns

Returns 0, or SEQ64_NULL_EVENT_INDEX if the iterator could not be decremented.

```
12.12.2.25 int seq64::eventslots::increment_top( ) [private]
```

Also handles the top-event index, so that the GUI can display the proper event numbers.

Returns

Returns the top index, or SEQ64_NULL_EVENT_INDEX if the iterator could not be incremented, or would increment to the end of the container.

```
12.12.2.26 int seq64::eventslots::decrement_current() [private]
```

Returns

Returns the decremented index, or SEQ64_NULL_EVENT_INDEX if the iterator could not be decremented. Remember that the index ranges only from 0 to m_line_count-1, and that is enforced here.

```
12.12.2.27 int seq64::eventslots::increment_current( ) [private]
```

Returns

Returns the incremented index, or SEQ64_NULL_EVENT_INDEX if the iterator could not be incremented. Remember that the index ranges only from 0 to m_line_count-1, and that is enforced here.

```
12.12.2.28 int seq64::eventslots::decrement_bottom() [private]
```

Returns

Returns 0, or SEQ64_NULL_EVENT_INDEX if the iterator could not be decremented.

```
12.12.2.29 int seq64::eventslots::increment_bottom( ) [private]
```

There is an issue in paging down using the scrollbar where, at the bottom of the scrolling, the bottom iterator ends up bad. Not yet sure how this happens, so for now we backtrack one event if this happens.

Returns

Returns the incremented index, or SEQ64 NULL EVENT INDEX if the iterator could not be incremented.

```
12.12.2.30 void seq64::eventslots::on_realize( ) [private]
```

It first calls the base-class version of on_realize(). Then it allocates any additional resources needed.

```
12.12.2.31 bool seq64::eventslots::on_expose_event ( GdkEventExpose * ev ) [private]
It draws all of the sequences.
12.12.2.32 bool seq64::eventslots::on_button_press_event ( GdkEventButton * ev ) [private]
12.12.2.33 bool seq64::eventslots::on_button_release_event( GdkEventButton * ev ) [private]
12.12.2.34 bool seq64::eventslots::on_focus_in_event( GdkEventFocus * ev ) [private]
See the same function in the perfroll module.
12.12.2.35 bool seq64::eventslots::on_focus_out_event ( GdkEventFocus * ev ) [private]
12.12.2.36 bool seq64::eventslots::on_scroll_event( GdkEventScroll * ev ) [private]
12.12.2.37 void seq64::eventslots::on_size_allocate ( Gtk::Allocation & a ) [private]
It first calls the base-class version of this function.
12.12.2.38 void seq64::eventslots::on_move_up() [private]
We must scroll up if the event is now before the frame, and should be made the new top event of the frame. Note
that this function isn't really an event-response callback. It is called byh eventedit::on key press event().
12.12.2.39 void seq64::eventslots::on_move_down() [private]
We must scroll down if the event is now after the frame. Note that this function isn't really an event-response
callback. It is called byh eventedit::on_key_press_event().
12.12.2.40 void seq64::eventslots::on_frame_up( ) [private]
12.12.2.41 void seq64::eventslots::on_frame_down() [private]
12.12.2.42 void seq64::eventslots::on_frame_home( ) [private]
12.12.2.43 void seq64::eventslots::on_frame_end( ) [private]
12.12.3 Friends And Related Function Documentation
```

12.12.3.1 friend class eventedit [friend]

12.12.4 Field Documentation

12.12.4.1 eventedit& seq64::eventslots::m_parent [private]

12.12.4.2 sequence& seq64::eventslots::m_seq [private]

12.12.4.3 editable_events seq64::**eventslots**::**m_event_container** [private]

12.12.4.4 int seq64::eventslots::m_slots_chars [private]

Pretty much hardwired to 64 at present. It helps determine the m_slots_x value (the width of the eventslots list).

```
12.12.4.5 int seq64::eventslots::m_char_w [private]
```

This value is obtained from a font-renderer accessor function.

```
12.12.4.6 int seq64::eventslots::m_setbox_w [private]
```

This used to be hardwired to 6 * 2 (character-width times two).

```
12.12.4.7 int seq64::eventslots::m_slots_x [private]
```

```
12.12.4.8 int seq64::eventslots::m_slots_y [private]
```

This value was once 22 pixels, but we need a little extra room for our new font. This extra room is compatible enough with the old font, as well.

```
12.12.4.9 int seq64::eventslots::m_event_count [private]
```

```
12.12.4.10 int seq64::eventslots::m_line_count [private]
```

12.12.4.11 int seq64::eventslots::m_line_maximum [private]

12.12.4.12 int seq64::eventslots::m_line_overlap [private]

12.12.4.13 int seq64::eventslots::m_top_index [private]

It is used in numbering the events that are shown in the event-slot frame. Do not confuse it with m_current_index, which is relative to the frame, not the container-beginning.

```
12.12.4.14 int seq64::eventslots::m_current_index [private]
```

This event will also be pointed to by the m_current_event iterator. Do not confuse it with m_top_index, which is relative to the container-beginning, not the frame.

```
12.12.4.15 editable_events::iterator seq64::eventslots::m_top_iterator [private]
```

12.12.4.16 editable_events::iterator seq64::eventslots::m_bottom_iterator [private]

12.12.4.17 editable_events::iterator seq64::eventslots::m_current_iterator [private]

12.12.4.18 int seq64::eventslots::m_pager_index [private]

12.13 seq64::font Class Reference

This class provides a wrapper for rendering fonts that are encoded as a 16 x 16 pixmap file in XPM format.

Public Types

Public Member Functions

• font ()

Rote default constructor, except that it does add 1 to the cf_text_h or co_text_h values to use in m_padded_h.

void init (Glib::RefPtr< Gdk::Window > windo)

Initialization function for a window on which fonts will be drawn.

void render_string_on_drawable (Glib::RefPtr< Gdk::GC > m_gc, int x, int y, Glib::RefPtr< Gdk::Drawable > drawable, const char *str, font::Color col, bool invert=false) const

Draws a text string.

• int char_width () const

'Getter' function for member m_font_w

• int char_height () const

'Getter' function for member m_font_h

int padded_height () const

'Getter' function for member m_padded_h

Private Attributes

· bool m use new font

If true, use the new font, which is a little bit more modern looking, and is also thicker, and thus a little easier to see.

int m_cell_w

Specifies the cell width of the whole character cell.

• int m_cell_h

Specfies the cell height of the whole character cell.

int m_font_w

Specifies the exact width of a character cell, in pixels.

• int m font h

Specifies the exact height of a character cell, in pixels.

int m_offset

Provides an ad hoc small horizontal or vertical offset for printing strings.

int m_padded_h

Provides a common constant used by much of the drawing code, but only marginally related to the padded character height.

const Glib::RefPtr< Gdk::Pixmap > * m_pixmap

Points to the current pixmap (m_black_pixmap or m_white_pixmap) to use to render a string.

Glib::RefPtr< Gdk::Pixmap > m black pixmap

The pixmap in the file $src/pixmaps/font_b.xpm$ is loaded into this object.

 $\bullet \ \, Glib::RefPtr < Gdk::Pixmap > m_white_pixmap \\$

The pixmap in the file src/pixmaps/font_w.xpm is loaded into this object.

• Glib::RefPtr< Gdk::Pixmap> m_b_on_y_pixmap

The pixmap in the file src/pixmaps/font_y.xpm is loaded into this object.

Glib::RefPtr< Gdk::Pixmap > m_y_on_b_pixmap

The pixmap in the file src/pixmaps/font_yb.xpm is loaded into this object.

 $\bullet \ \, Glib::RefPtr < Gdk::Pixmap > m_b_on_c_pixmap \\$

The pixmap in the file src/pixmaps/cyan_wenfont_y.xpm is loaded into this object.

Glib::RefPtr< Gdk::Pixmap > m_c_on_b_pixmap

The pixmap in the file src/pixmaps/cyan_wenfont_yb.xpm is loaded into this object.

Glib::RefPtr< Gdk::Bitmap > m_clip_mask

This object is instantiated as a default object.

12.13.1 Member Enumeration Documentation

12.13.1.1 enum seq64::font::Color

Basically, these two values cause the selection of one or another pixmap (font_b_xpm and font_w_xpm). We've added two more pixmaps to draw black text on a yellow background (font_y.xpm) and yellow text on a black background (font_yb.xpm). Oh, and couple more for cyan and black text-blitting.

Enumerator

BLACK The first supported color. A black font on a white background.

WHITE The second supported color. A white font on a black background.

BLACK_ON_YELLOW A new color, for drawing black text on a yellow background.

YELLOW_ON_BLACK A new color, for drawing yellow text on a black background.

BLACK_ON_CYAN A new color, for drawing black text on a cyan background.

CYAN_ON_BLACK A new color, for drawing cyan text on a black background.

12.13.2 Constructor & Destructor Documentation

```
12.13.2.1 seq64::font::font()
```

12.13.3 Member Function Documentation

```
12.13.3.1 void seq64::font::init ( Glib::RefPtr< Gdk::Window> wp )
```

This function loads four pixmaps that contain the characters to be used to draw text strings.

One pixmap has white characters on a black background, one has black characters on a white background, one has yellow characters on a black background, and one has black characters on a yellow background.

Parameters

wp	Provides the windows pointer for the window that holds the color map.
----	---

12.13.3.2 void seq64::font::render_string_on_drawable (Glib::RefPtr< Gdk::GC > gc, int x, int y, Glib::RefPtr< Gdk::Drawable > a_draw , const char * str, font::Color col, bool invert = false) const

This function grabs the proper font bitmap, extracts the current character pixmap from it, and slaps it down where it needs to be to render the character in the string.

Parameters

gc	Provides the graphics context for drawing the text using GTK+.
Х	The horizontal location of the text.
У	The vertical location of the text.
a_draw	The drawable object on which to draw the text.
str	The string to draw. Should use a constant string reference instead.

col	The font color to use to draw the string. The supported values are font::BLACK, font::WHITE, font::BLACK_ON_YELLOW, font::YELLOW_ON_BLACK. The actual correct colors are provided by selecting one of four font pixmaps, as described in the init() function.
invert	If true, apply color inversion, if specified.

```
12.13.3.3 int seq64::font::char_width() const [inline]

12.13.3.4 int seq64::font::char_height() const [inline]

12.13.3.5 int seq64::font::padded_height() const [inline]

12.13.4 Field Documentation

12.13.4.1 bool seq64::font::m_use_new_font [private]

12.13.4.2 int seq64::font::m_cell_w [private]

12.13.4.3 int seq64::font::m_cell_h [private]

12.13.4.4 int seq64::font::m_font_w [private]
```

Currently defaults to cf_text_w = 6. Note that a lot of stuff depends on this being 6 at present, even with our new, slightly wider, font.

```
12.13.4.5 int seq64::font::m_font_h [private]
```

Currently defaults to $cf_{text_h} = 10$. Note that a lot of stuff depends on this being 10 at present, even with our new, slightly wider, font. But some of the drawing code doesn't use the character height, but the padded character height.

```
12.13.4.6 int seq64::font::m_offset [private]

12.13.4.7 int seq64::font::m_padded_h [private]

12.13.4.8 const Glib::RefPtr<Gdk::Pixmap>* seq64::font::m_pixmap [mutable], [private]
```

This member used to be an object, but it's probably a bit faster to just use a pointer (or a reference).

```
12.13.4.9 Glib::RefPtr<Gdk::Pixmap> seq64::font::m_black_pixmap [private]
```

It contains a black font on a white background. The new-style font, if selected, is in the resources/pixmaps/wenfont ← _b.xmp pixmap.

```
12.13.4.10 Glib::RefPtr < Gdk::Pixmap > seq64::font::m_white_pixmap [private]
```

It contains a black font on a white background. The new-style font, if selected, is in the resources/pixmaps/wenfont ← _w.xmp pixmap.

```
12.13.4.11 Glib::RefPtr<Gdk::Pixmap> seq64::font::m_b_on_y_pixmap [private]
```

It contains a black font on a yellow background. The new-style font, if selected, is in the resources/pixmaps/wenfont ← _y.xmp pixmap.

```
12.13.4.12 Glib::RefPtr<Gdk::Pixmap> seq64::font::m_y_on_b_pixmap [private]
```

It contains a yellow font on a black background. The new-style font, if selected, is resources/pixmaps/wenfont ←
_yb.xmp pixmap.

```
12.13.4.13 Glib::RefPtr < Gdk::Pixmap > seq64::font::m_b_on_c_pixmap [private]
```

It contains a black font on a cyan background. It is available only for the new font-style.

```
12.13.4.14 Glib::RefPtr < Gdk::Pixmap > seq64::font::m_c_on_b_pixmap [private]
```

It contains a cyan font on a black background. It is available only for the new font-style.


```
12.13.4.15 Glib::RefPtr<Gdk::Bitmap> seq64::font::m_clip_mask [private]
```

All we know is it seems to be a requirement for creating a pixmap object from an XMP file.

12.14 seg64::FruityPerfInput Class Reference

Implements the performance input of that certain fruity sequencer that people seem to like.

Inheritance diagram for seq64::FruityPerfInput:



Public Member Functions

• FruityPerfInput ()

Default constructor.

bool on button press event (GdkEventButton *ev, perfroll &roll)

Handles a button-press event in the Fruity manner.

• bool on_button_release_event (GdkEventButton *ev, perfroll &roll)

Handles a button-release event.

• bool on_motion_notify_event (GdkEventMotion *ev, perfroll &roll)

Handles a Fruity motion-notify event.

Private Member Functions

· void update mouse pointer (perfroll &roll)

Updates the mouse pointer, implementing a context-sensitive mouse.

bool on_left_button_pressed (GdkEventButton *ev, perfroll &roll)

Handles the left button of the mouse.

• bool on_right_button_pressed (GdkEventButton *ev, perfroll &roll)

Handles the right button of the mouse.

Private Attributes

• long m_current_x

The current x value of the mouse.

long m_current_y

The current y value of the mouse.

Friends

· class perfroll

Additional Inherited Members

12.14.1 Constructor & Destructor Documentation

```
12.14.1.1 seq64::FruityPerfInput::FruityPerfInput() [inline]
```

12.14.2 Member Function Documentation

12.14.2.1 bool seq64::FruityPerfInput::on_button_press_event (GdkEventButton * ev, perfroll & roll) [virtual]

Parameters

ev	The button-press event to process.
roll	The song editor piano roll that is the "parent" of this class.

Returns

Returns true if a modification occurred.

Implements seq64::AbstractPerfInput.

12.14.2.2 bool seq64::FruityPerfInput::on_button_release_event (GdkEventButton * ev, perfroll & roll) [virtual]

Why is m_adding_pressed modified conditionally when the same modification is then made unconditionally?

Parameters

ev	The button-release event to process.
roll	The song editor piano roll that is the "parent" of this class.

Returns

Returns true if a modification occurred.

Implements seq64::AbstractPerfInput.

12.14.2.3 bool seq64::FruityPerfInput::on_motion_notify_event(GdkEventMotion * ev, perfroll & roll) [virtual]

Parameters

ev	The motion-notify event to process.
rol	The song editor piano roll that is the "parent" of this class.

Returns

Returns true if a modification occurred, and sets the perform modified flag based on that result.

Implements seq64::AbstractPerfInput.

12.14.2.4 void seq64::FruityPerfInput::update_mouse_pointer(perfroll & roll) [private]

Note that perform::convert_xy() returns its values via side-effects on the last two parameters.

Parameters

roll The song editor piano roll that is the "parent" of this class.

12.14.2.5 bool seq64::FruityPerfInput::on_left_button_pressed (GdkEventButton * ev, perfroll & roll) [private]

It can handle splitting triggers (?), adding notes, and the following clicks to resize the event, or move it, depending on where clicked:

- clicked left side: begin a grow/shrink for the left side
- clicked right side: grow/shrink the right side
- clicked in the middle move it

I don't get it, though... all three buttons are handled in the generic button-press callback. Oh, this is just a helper function.

Parameters

ev	The left-button-press event to process.
roll	The song editor piano roll that is the "parent" of this class.

Returns

Now returns true if a modification occurred.

12.14.2.6 bool seq64::FruityPerfInput::on_right_button_pressed (GdkEventButton * ev, perfroll & roll) [private]

I don't get it, though... all three buttons are handled in the generic button-press callback. Oh, this is a helper function.

ev	The right-button-press event to process.
roll	The song editor piano roll that is the "parent" of this class.

Returns

Returns true if a modification occurred.

12.14.3 Friends And Related Function Documentation

```
12.14.3.1 friend class perfroll [friend]
```

12.14.4 Field Documentation

```
12.14.4.1 long seq64::FruityPerfInput::m_current_x [private]
```

12.14.4.2 long seq64::FruityPerfInput::m_current_y [private]

12.15 seq64::FruitySeqEventInput Struct Reference

This structure implements the interaction methods for the "fruity" mode of operation.

Public Member Functions

• FruitySeqEventInput ()

Default constructor.

void update_mouse_pointer (seqevent &ths)

Provides support for a context-sensitive mouse.

 $\bullet \ \ bool\ on_button_press_event\ (GdkEventButton\ *ev,\ seqevent\ \&ths)$

Implements the on-button-press event callback.

• bool on_button_release_event (GdkEventButton *ev, seqevent &ths)

Implements the on-button-release callback.

• bool on_motion_notify_event (GdkEventMotion *ev, seqevent &ths)

Implements the on-motion-notify callback.

Data Fields

· bool m justselected one

Indicates that the left mouse button was click to start a selection.

bool m_is_drag_pasting_start

Set to true when the mouse button is pressed and we're starting to drag some notes to move them and paste them to a different location.

bool m_is_drag_pasting

Set to true when the left mouse button is pressed for dragging and pasting, set to false when the mouse button is released to drop the pasted items.

- 12.15.1 Constructor & Destructor Documentation
- **12.15.1.1** seq64::FruitySeqEventInput::FruitySeqEventInput () [inline]
- 12.15.2 Member Function Documentation
- 12.15.2.1 void seq64::FruitySeqEventInput::update_mouse_pointer (seqevent & seqev)

seqev	Provides the seqevent pane (actually a strip on the seqedit window) to update to show the proper
	mouse cursor (left pointer, center pointer, and pencil).

12.15.2.2 bool seq64::FruitySeqEventInput::on_button_press_event (GdkEventButton * ev, seqevent & seqev)

Handles dragging and other actions.

The first thing is to set the values for dragging, then reset the box that holds the dirty redraw spot. If pasting, undo the clipboard, and paste the selected events.

Otherwise, process the mouse actions. The current steps shown below are my initial guesses, to be verified at some point.

1. Left button:

- (a) Click:
 - i. A click and release without a drag, or without a Ctrl-Shift, deselects the events.
 - ii. A direct click on an event selects only that event.
- (b) Click-drag:
 - i. If events already selected, adds note and length to the selected notes.
 - ii. Otherwise, select the notes and events.
 - iii. If no events selected in the end, undo the selection.
- · Ctrl-left button:
 - TODO.

The opening part of this function matches that of Seq24SeqEventInput :: on_button_press_event().

Parameters

ev	The button event for the press of a mouse button.
seqev	Provides the sequeent strip to be affected by this button event.

Returns

Returns true if a modification was made. It used to return true all the time.

12.15.2.3 bool seq64::FruitySeqEventInput::on_button_release_event (GdkEventButton * ev, seqevent & seqev)

Parameters

ev	The button event for the press of a mouse button.
seqev	Provides the seqevent strip to be affected by this button event.

Returns

Returns true if a modification was made. It used to return true all the time.

12.15.2.4 bool seq64::FruitySeqEventInput::on_motion_notify_event (GdkEventMotion * ev, seqevent & seqev)

Parameters

ev	The button event for the press of a mouse button.
seqev	Provides the sequeent strip to be affected by this button event.

Returns

Returns true if a modification occurred, and sets the perform modified flag based on that result.

12.15.3 Field Documentation

- 12.15.3.1 bool seq64::FruitySeqEventInput::m_justselected_one
- 12.15.3.2 bool seq64::FruitySeqEventInput::m_is_drag_pasting_start
- 12.15.3.3 bool seq64::FruitySeqEventInput::m_is_drag_pasting

12.16 seq64::FruitySeqRollInput Class Reference

Implements the fruity mouse interaction paradigm for the segroll.

Public Member Functions

- FruitySeqRollInput ()
 - Default constructor.
- void update_mouse_pointer (seqroll &ths)

Updates the mouse pointer, implementing a context-sensitive mouse.

- bool on_button_press_event (GdkEventButton *ev, seqroll &ths)
 - Implements the fruity on-button-press callback.
- bool on_button_release_event (GdkEventButton *ev, seqroll &ths)
 - Implements the fruity handling for the on-button-release event.
- bool on_motion_notify_event (GdkEventMotion *ev, seqroll &ths)
 - Implements the fruity handling for the on-motion-notify event.

Private Attributes

· bool m erase painting

Set to tru if we hold the right mouse button down (in "fruity" mode) and start to drag the mouse around, erasing notes.

int m_drag_paste_start_pos [2]

Holds the original position of the mouse when ctrl-left-click-drag is done, and is used to make sure that the action doesn't occur until a movement of at least 6 pixels has occurred, to avoid unintended actions caused by minimal jitter in the user's hands.

12.16.1 Constructor & Destructor Documentation

12.16.1.1 seq64::FruitySeqRollInput::FruitySeqRollInput() [inline]

12.16.2 Member Function Documentation

12.16.2.1 void seq64::FruitySeqRollInput::update_mouse_pointer (seqroll & sroll)

Parameters

parent" of this interaction class.	sroll Provides the
------------------------------------	--------------------

12.16.2.2 bool seq64::FruitySeqRollInput::on_button_press_event (GdkEventButton * ev, seqroll & sroll)

This function now uses the needs update flag to determine if the perform object should modify().

Parameters

ev	The button event.
sroll	The parent of this "fruity" interaction class.

Returns

Returns the value of needs_update. It used to return only true.

12.16.2.3 bool seq64::FruitySeqRollInput::on_button_release_event (GdkEventButton * ev, seqroll & sroll)

Parameters

ev	The button event.
sroll	The parent of this "fruity" interaction class.

Returns

Returns the value of needs_update. It used to return only true.

If in moving mode, adjust for snap and convert deltas into screen coordinates. Since delta_note was from delta_y, it will be flipped (delta_y[0] = note[127], etc.), so we have to adjust.

12.16.2.4 bool seq64::FruitySeqRollInput::on_motion_notify_event (GdkEventMotion * ev, seqroll & sroll)

Parameters

ev	The motion event.
sroll	The parent of this "fruity" interaction class. (Why not just inherit and save all these indirect accesses to
	the seqroll? Well, that would make it more difficult to change the mode of interation, in the Options
	menu, on the fly.)

Generated by Doxygen

Returns

Returns the value of needs_update.

In "fruity" interaction mode, ctrl-left-click-drag on selected note(s) starts a copy/unselect/paste. Doesn't begin the paste until the mouse moves a few pixels, to filter out the unsteady hand.


12.16.3 Field Documentation

- **12.16.3.1** bool seq64::FruitySeqRollInput::m_erase_painting [private]
- 12.16.3.2 int seq64::FruitySeqRollInput::m_drag_paste_start_pos[2] [private]

12.17 seq64::gui_assistant Class Reference

This class provides an interface for some of the GUI support needed in Sequencer64.

Inheritance diagram for seq64::gui assistant:



Public Member Functions

• gui_assistant (keys_perform &kp)

This constructor wires in some externally (for now) created objects.

virtual ~gui_assistant ()

Stock base-class implementation of a virtual destructor.

- virtual void quit ()=0
- virtual void jack idle connect (jack assistant &jack)=0
- virtual void lash_timeout_connect (lash *lashobject)=0
- const keys_perform & keys () const

'Getter' function for member $m_{keys_perform}$ The const getter.

keys_perform & keys ()

'Getter' function for member m_keys_perform The un-const getter.

Private Attributes

keys_perform & m_keys_perform

Provides a reference to the app-specific GUI-specific keys_perform-derived object that an application is going to use for handling sequence-control keys.

12.17.1 Detailed Description

It also contain a number of helper objects that all kind of go together; only this assistant object will need to be passed around (by non-GUI code).

12.17.2 Constructor & Destructor Documentation

12.17.2.1 seq64::gui_assistant::gui_assistant (keys_perform & kp)

Parameters

kp Provides a set of key codes to be used by the perform object to control patterns and their performance.

```
12.17.2.2 virtual seq64::gui_assistant::~gui_assistant( ) [inline], [virtual]
```

12.17.3 Member Function Documentation

```
12.17.3.1 virtual void seq64::gui_assistant::quit( ) [pure virtual]
```

Implemented in seq64::gui_assistant_gtk2.

12.17.3.2 virtual void seq64::gui_assistant::jack_idle_connect(jack_assistant & jack) [pure virtual]

Implemented in seq64::gui_assistant_gtk2.

```
12.17.3.3 virtual void seq64::gui_assistant::lash_timeout_connect( lash * lashobject ) [pure virtual]

Implemented in seq64::gui_assistant_gtk2.

12.17.3.4 const keys_perform& seq64::gui_assistant::keys( ) const [inline]
```

12.17.4 Field Documentation


12.17.4.1 keys_perform& seq64::gui_assistant::m_keys_perform [private]

12.18 seq64::gui_assistant_gtk2 Class Reference

12.17.3.5 keys_perform& seq64::gui_assistant::keys() [inline]

This class provides an interface for some of the Gtk/Gdk/Glib support needed in Sequencer64.

Inheritance diagram for seq64::gui_assistant_gtk2:



Public Member Functions

• gui_assistant_gtk2 ()

This class provides an interface for some of the Gtk/Gdk/Glib support needed in Sequencer64.

virtual ~gui_assistant_gtk2 ()

Virtual classes require a virtual destructor.

• virtual void quit ()

Calls the Glib Main object's quit() function.

virtual void lash_timeout_connect (lash *lashobject)

Connects the LASH timeout-event callback to the Glib timeout object.

virtual void jack_idle_connect (jack_assistant &jack)

Connects the JACK session-event callback to the Glib idle object.

Static Private Attributes

static keys_perform_gtk2 sm_internal_keys
 Provides a pre-made keys_perform object.

12.18.1 Constructor & Destructor Documentation

```
12.18.1.1 seq64::gui_assistant_gtk2::gui_assistant_gtk2 ( )
```

```
12.18.1.2 virtual seq64::gui_assistant_gtk2::~gui_assistant_gtk2( ) [inline], [virtual]
```

12.18.2 Member Function Documentation

```
12.18.2.1 void seq64::gui_assistant_gtk2::quit( ) [virtual]
```

Implements seq64::gui_assistant.

```
12.18.2.2 void seq64::gui_assistant_gtk2::lash_timeout_connect( lash * lashobject ) [virtual]
```

The time-out value is set to 250 ms.

Implements seq64::gui_assistant.

```
12.18.2.3 void seq64::gui_assistant_gtk2::jack_idle_connect( jack_assistant & jack ) [virtual]
```

If JACK session support is not enabled, we might emit a message. This mainly prevents a compiler warning about an unused parameter.

Implements seq64::gui_assistant.

12.18.3 Field Documentation


12.18.3.1 keys_perform_gtk2 seq64::gui_assistant_gtk2::sm_internal_keys [static], [private]

This object is set into the reference provided in the gui_assistant base class.

12.19 seq64::gui_drawingarea_gtk2 Class Reference

Implements the basic drawing areas of the application.

Inheritance diagram for seq64::gui_drawingarea_gtk2:



Data Structures

struct rect

A small helper structure representing a rectangle.

Public Member Functions

• gui_drawingarea_gtk2 (perform &p, int window_x=0, int window_y=0)

Perform-only constructor.

• gui_drawingarea_gtk2 (perform &a_perf, Gtk::Adjustment &a_hadjust, Gtk::Adjustment &a_vadjust, int window_x=0, int window_y=0)

Principal constructor.

virtual ~gui_drawingarea_gtk2 ()

Provides a destructor to delete allocated objects.

int window_x () const

'Getter' function for member m window x

int window_y () const

'Getter' function for member m_window_y

• int current_x () const

'Getter' function for member m_current_x

• int current y () const

'Getter' function for member m_current_y

int drop_x () const

'Getter' function for member m_drop_x

int drop_y () const

'Getter' function for member m_drop_y

Protected Member Functions

virtual void force draw ()

Provides a common function for redrawing.

• perform & perf ()

'Getter' function for member m_mainperf

void clear_window ()

Clears the main window.

void set_line (Gdk::LineStyle ls, int width=1)

A small wrapper function for readability in line-drawing.

void draw line (int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on the window.

• void draw_line (const Color &c, int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on the window after setting the given foreground color.

void draw_line_on_pixmap (int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on the pixmap.

void draw_line_on_pixmap (const Color &c, int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on the pixmap after setting the given foreground color.

void draw_line (Glib::RefPtr< Gdk::Pixmap > &pixmap, int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on any pixmap (not a drawable, though, due to a compiler error after setting the given foreground color.

void draw_line (Glib::RefPtr< Gdk::Pixmap > &pixmap, const Color &c, int x1, int y1, int x2, int y2)

 $\label{eq:Asmall wrapper function to draw\ a\ line\ on\ the\ pixmap\ after\ setting\ the\ given\ foreground\ color.$

• void draw line (Glib::RefPtr< Gdk::Drawable > &drawable, int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on any pixmap (not a drawable, though, due to a compiler error after setting the given foreground color.

void draw line (Glib::RefPtr< Gdk::Drawable > &drawable, const Color &c, int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on the drawable after setting the given foreground color.

void render_string (int x, int y, const std::string &s, font::Color color, bool invert=false)

A small wrapper function for readability in string-drawing to the window.

void render string on pixmap (int x, int y, const std::string &s, font::Color color, bool invert=false)

A small wrapper function for readability in string-drawing to the pixmap.

• void draw_rectangle (int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on the window.

void draw_rectangle (const Color &c, int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing.

• void draw rectangle (Glib::RefPtr< Gdk::Drawable > &drawable, int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on a "drawable" context, where the foreground color has already been specified.

void draw_rectangle (Glib::RefPtr< Gdk::Drawable > &drawable, const Color &c, int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on any drawable context.

void draw_rectangle (Glib::RefPtr< Gdk::Pixmap > &pixmap, int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on a "pixmap" context, where the foreground color has already been specified.

• void draw_rectangle (Glib::RefPtr< Gdk::Pixmap > &pixmap, const Color &c, int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on any pixmap context.

void draw_rectangle_on_pixmap (int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on the pixmap.

• void draw_rectangle_on_pixmap (const Color &c, int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on the pixmap.

• void draw_normal_rectangle_on_pixmap (int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on the pixmap.

· void draw drawable (int xsrc, int ysrc, int xdest, int ydest, int width, int height)

Provides the most common use case for redrawing.

· void scroll hadjust (Gtk::Adjustment &hadjust, double step)

This function provides optimization for the on_scroll_event() functions, and should provide support for having the seqedit/seqroll/seqtime/seqdata panes follow the scrollbar, in a future upgrade (now partly in place).

void scroll vadjust (Gtk::Adjustment &vadjust, double step)

This function is the vertical version of the scroll_hadjust() function, intended for adding keystroke vertical scrolling using the Page-Up and Page-Down keys, as a new feature of Sequencer64.

- void scroll_hset (Gtk::Adjustment &hadjust, double value)
- void scroll vset (Gtk::Adjustment &vadjust, double value)
- void set_current_drop_x (int x)

Sets the current x value and the drop x value.

void set_current_drop_y (int y)

Sets the current y value and the drop y value.

void on_realize ()

For this GTK callback, on realization of window, initialize the shiz.

Protected Attributes

Glib::RefPtr< Gdk::GC > m gc

The graphics context, which is required for ever drawing and rendering operation.

Glib::RefPtr< Gdk::Window > m_window

Provides the default "window".

· Gtk::Adjustment & m vadjust

Provides an object for vertical "adjustments".

Gtk::Adjustment & m_hadjust

Provides an object for horizontal "adjustments".

Glib::RefPtr< Gdk::Pixmap > m pixmap

Provides the default "pixmap".

Glib::RefPtr< Gdk::Pixmap > m_background

Another pixmap, used for backgrounds.

Glib::RefPtr< Gdk::Pixmap > m foreground

Another pixmap, used for foregrounds.

perform & m_mainperf

A frequent hook into the main perform object.

• int m_window_x

Window sizes.

• int m_window_y

Window height value.

• int m current x

The x and y value of the current location of the mouse (during dragging?)

· int m current y

Current mouse y value.

• int m_drop_x

These values are used when roping and highlighting a bunch of events.

• int m_drop_y

Current mouse y-drop value.

Private Member Functions

- gui_drawingarea_gtk2 (const gui_drawingarea_gtk2 &)
- gui_drawingarea_gtk2 & operator= (const gui_drawingarea_gtk2 &)
- void gtk_drawarea_init ()

Does basic initialization for each of the constructors.

Additional Inherited Members

12.19.1 Detailed Description

Note that this class really "isn't" a gui_pallete_gtk2; it should simply "have" one. But that base class must be derived from Gtk::DrawingArea. We don't want to waste some space by using a "has-a" relationship, and also put up with having to access the palette indirectly. So, in this case, we tolerate the less strict implementation.

12.19.2 Constructor & Destructor Documentation

12.19.3.2 int seq64::gui_drawingarea_gtk2::window_x () const [inline]

```
12.19.2.1 seq64::gui_drawingarea_gtk2::gui_drawingarea_gtk2 ( const gui_drawingarea_gtk2 & ) [private]
12.19.2.2 seq64::gui_drawingarea_gtk2::gui_drawingarea_gtk2 ( perform & p, int window_x = 0, int window_y = 0 )
12.19.2.3 seq64::gui_drawingarea_gtk2::gui_drawingarea_gtk2 ( perform & a_perf, Gtk::Adjustment & a_hadjust, Gtk::Adjustment & a_vadjust, int window_x = 0, int window_y = 0 )
12.19.2.4 seq64::gui_drawingarea_gtk2::~gui_drawingarea_gtk2 ( ) [virtual]
12.19.3.1 Member Function Documentation
12.19.3.1 gui_drawingarea_gtk2& seq64::gui_drawingarea_gtk2::operator=( const gui_drawingarea_gtk2 & ) [private]
```

```
12.19.3.3 int seq64::gui_drawingarea_gtk2::window_y( ) const [inline]

12.19.3.4 int seq64::gui_drawingarea_gtk2::current_x( ) const [inline]

12.19.3.5 int seq64::gui_drawingarea_gtk2::current_y( ) const [inline]

12.19.3.6 int seq64::gui_drawingarea_gtk2::drop_x( ) const [inline]

12.19.3.7 int seq64::gui_drawingarea_gtk2::drop_y( ) const [inline]

12.19.3.8 virtual void seq64::gui_drawingarea_gtk2::force_draw( ) [inline], [protected], [virtual]
```

This function forces a redraw. Some classes extend this function.

Reimplemented in seq64::seqroll, seq64::seqevent, and seq64::seqkeys.

```
12.19.3.9 perform& seq64::gui_drawingarea_gtk2::perf( ) [inline], [protected]
12.19.3.10 void seq64::gui_drawingarea_gtk2::clear_window( ) [inline], [protected]
```

One less need to access m_window directly.

12.19.3.11 void seq64::gui_drawingarea_gtk2::set_line(Gdk::LineStyle /s, int width = 1) [inline], [protected]

Sets the attributes of a line to be drawn.

Parameters

	ls	Provides the Gtk-specific line style.
ĺ	width	Provides the width of the line to be drawn. It defaults to the most common value, 1.

12.19.3.12 void seq64::gui_drawingarea_gtk2::draw_line(int x1, int y1, int x2, int y2) [inline], [protected]

Parameters

x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.19.3.13 void seq64::gui_drawingarea_gtk2::draw_line (const Color & c, int x1, int y1, int x2, int y2) [protected]

С	The foreground color in which to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.19.3.14 void seq64::gui_drawingarea_gtk2::draw_line_on_pixmap (int x1, int y1, int x2, int y2) [inline], [protected]

Parameters

x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.19.3.15 void seq64::gui_drawingarea_gtk2::draw_line_on_pixmap (const Color & c, int x1, int y1, int x2, int y2) [protected]

Parameters

С	The foreground color in which to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.19.3.16 void seq64::gui_drawingarea_gtk2::draw_line (Glib::RefPtr< Gdk::Pixmap > & pixmap, int x1, int y1, int x2, int y2
) [inline], [protected]

Parameters

pixmap	Provides the Gdk::Pixmap pointer needed to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.19.3.17 void seq64::gui_drawingarea_gtk2::draw_line (Glib::RefPtr < Gdk::Pixmap > & pixmap, const Color & c, int x1, int y1, int x2, int y2) [protected]

pixmap	Provides the Gdk::Drawable pointer needed to draw the line.
С	The foreground color in which to draw the line.

x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.19.3.18 void seq64::gui_drawingarea_gtk2::draw_line (Glib::RefPtr< Gdk::Drawable > & drawable, int x1, int y1, int x2, int y2) [inline], [protected]

Parameters

drawable	Provides the Gdk::Drawable pointer needed to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.19.3.19 void seq64::gui_drawingarea_gtk2::draw_line (Glib::RefPtr< Gdk::Drawable > & drawable, const Color & c, int x1, int x2, int y2) [protected]

Parameters

drawable	Provides the Gdk::Drawable pointer needed to draw the line.
С	The foreground color in which to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.19.3.20 void seq64::gui_drawingarea_gtk2::render_string (int x, int y, const std::string & s, font::Color color, bool invert = false) [inline], [protected]

Parameters

X	The x-coordinate of the origin.
У	The y-coordinate of the origin.
s	The string to be drawn.
color	The color with which to draw the string.
invert	If true, apply color inversion, if active. Defaults to false.

12.19.3.21 void seq64::gui_drawingarea_gtk2::render_string_on_pixmap (int x, int y, const std::string & s, font::Color color, bool invert = false) [inline], [protected]

X	The x-coordinate of the origin.

У	The y-coordinate of the origin.
s	The string to be drawn.
color	The color with which to draw the string.
invert	If true, apply color inversion, if active. Defaults to false.

12.19.3.22 void seq64::gui_drawingarea_gtk2::draw_rectangle(int x, int y, int lx, int ly, bool fill = true) [inline], [protected]

Parameters

Х	The x-coordinate of the origin.
У	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults
	to true.

12.19.3.23 void seq64::gui_drawingarea_gtk2::draw_rectangle (const Color & c, int x, int y, int lx, int ly, bool fill = true)

[protected]

It adds setting the foreground color to the draw_rectangle() function.

Parameters

С	Provides the foreground color to set.
Х	The x-coordinate of the origin.
У	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults
	to true.

12.19.3.24 void seq64::gui_drawingarea_gtk2::draw_rectangle (Glib::RefPtr< Gdk::Drawable > & drawable, int x, int y, int lx, int ly, bool fill = true) [inline], [protected]

drawable	The object on which to draw the rectangle.
X	The x-coordinate of the origin.
У	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color).
	Defaults to true.

12.19.3.25 void seq64::gui_drawingarea_gtk2::draw_rectangle (Glib::RefPtr< Gdk::Drawable > & drawable, const Color & c, int x, int y, int lx, int ly, bool fill = true) [protected]

It also supports setting the foreground color to the draw_rectangle() function.

We have a number of such functions: for the main window, for the main pixmap, and for any drawing surface. Is the small bit of conciseness worth it?

Parameters

drawable	The surface on which to draw the box.
С	Provides the foreground color to set.
X	The x-coordinate of the origin.
У	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults to true.

12.19.3.26 void seq64::gui_drawingarea_gtk2::draw_rectangle (Glib::RefPtr < Gdk::Pixmap > & pixmap, int x, int y, int lx, int ly, bool fill = true) [inline], [protected]

Parameters

pixmap	The object on which to draw the rectangle.
Х	The x-coordinate of the origin.
У	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color).
	Defaults to true.

12.19.3.27 void seq64::gui_drawingarea_gtk2::draw_rectangle (Glib::RefPtr < Gdk::Pixmap > & pixmap, const Color & c, int x, int y, int lx, int ly, bool fill = true) [protected]

It also supports setting the foreground color to the draw_rectangle() function.

We have a number of such functions: for the main window, for the main pixmap, and for any drawing surface. Is the small bit of conciseness worth it?

pixmap	The surface on which to draw the box.
С	Provides the foreground color to set.
Х	The x-coordinate of the origin.
У	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults to true.

12.19.3.28 void seq64::gui_drawingarea_gtk2::draw_rectangle_on_pixmap (int x, int y, int lx, int ly, bool fill = true)
[inline], [protected]

Parameters

X	The x-coordinate of the origin.
У	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults
	to true.

12.19.3.29 void seq64::gui_drawingarea_gtk2::draw_rectangle_on_pixmap (const Color & c, int x, int y, int lx, int ly, bool fill = true) [protected]

It adds setting the foreground color to the draw_rectangle() function.

Parameters

С	Provides the foreground color to set.	
Х	The x-coordinate of the origin.	
У	The y-coordinate of the origin.	
lx	The width of the box.	
ly	The height of the box.	
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults	
	to true.	

12.19.3.30 void seq64::gui_drawingarea_gtk2::draw_normal_rectangle_on_pixmap (int x, int y, int lx, int ly, bool fill = true) [protected]

It uses Gtk to get the proper background styling for the rectangle.

Parameters

Х	The x-coordinate of the origin.	
У	The y-coordinate of the origin.	
lx	The width of the box.	
ly	The height of the box.	
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults	
	to true.	

12.19.3.31 void seq64::gui_drawingarea_gtk2::draw_drawable (int xsrc, int ysrc, int xdest, int ydest, int width, int height)
[inline], [protected]

12.19.3.32 void seq64::gui_drawingarea_gtk2::scroll_hadjust(Gtk::Adjustment & hadjust, double step) [protected]

This function is currently duplicated in the gui_drawingarea_gtk2 and gui_window_gtk2 modules.

hadjust	Provides a reference to the adjustment object to be adjusted. Do we really need this to be a parameter? Why not just use the m_hadjust member? (Note that this member is not present in the similar gui_window_gtk2 class.)	
step	Provides the step value to use for adjusting the horizontal scrollbar. If negative, the adjustment is leftward. If positive, the adjustment is rightward. It can be the value of m_hadjust->get_step_increment(), or provided especially to keep up with the progress bar.	

12.19.3.33 void seq64::gui_drawingarea_gtk2::scroll_vadjust (Gtk::Adjustment & vadjust, double step) [protected]

Parameters

vadjust	Provides a reference to the adjustment object to be adjusted.
step	Provides the step value to use for adjusting the vertical scrollbar. If negative, the adjustment is upward. If positive, the adjustment is downward. It can be the value of m_vadjust->get_step_increment().

12.19.3.34 void seq64::gui_drawingarea_gtk2::scroll_hset (Gtk::Adjustment & hadjust, double value) [protected]

12.19.3.35 void seq64::gui_drawingarea_gtk2::scroll_vset (Gtk::Adjustment & vadjust, double value) [protected]

12.19.3.36 void seq64::gui_drawingarea_gtk2::set_current_drop_x(int x) [inline], [protected]

Parameters

x The x value to be set.

12.19.3.37 void seq64::gui_drawingarea_gtk2::set_current_drop_y(inty) [inline], [protected]

Parameters

```
y The y value to be set.
```

12.19.3.38 void seq64::gui_drawingarea_gtk2::gtk_drawarea_init() [private]

12.19.3.39 void seq64::gui_drawingarea_gtk2::on_realize() [protected]

It allocates any additional resources that weren't initialized in the constructor.

12.19.4 Field Documentation

12.19.4.1 Glib::RefPtr < Gdk::GC > seq64::gui_drawingarea_gtk2::m_gc [protected]

12.19.4.2 Glib::RefPtr<Gdk::Window> seq64::gui_drawingarea_gtk2::m_window [protected]

Wrapper functions with undecorated wrapper names are used for accessing this item. We hope to be able to hide this items completely some day.

```
12.19.4.3 Gtk::Adjustment& seq64::gui_drawingarea_gtk2::m_vadjust [protected]
12.19.4.4 Gtk::Adjustment& seq64::gui_drawingarea_gtk2::m_hadjust [protected]
12.19.4.5 Glib::RefPtr<Gdk::Pixmap> seq64::qui_drawingarea_gtk2::m_pixmap [protected]
Wrapper functions with undecorated wrapper names are used for accessing this item. We hope to be able to hide
this items completely some day.
12.19.4.6 Glib::RefPtr<Gdk::Pixmap> seq64::gui_drawingarea_gtk2::m_background [protected]
Our wrappers still leave this member exposed (giggle).
12.19.4.7 Glib::RefPtr < Gdk::Pixmap > seq64::gui_drawingarea_gtk2::m_foreground [protected]
Our wrappers still leave this member exposed.
12.19.4.8 perform& seq64::gui_drawingarea_gtk2::m_mainperf [protected]
We could move this into yet another base class, since a number of classes don't need it. Probably not worth the
effort at this time.
12.19.4.9 int seq64::gui_drawingarea_gtk2::m_window_x [protected]
Could make this constant, but some windows are resizable. Window width value.
12.19.4.10 int seq64::gui_drawingarea_gtk2::m_window_y [protected]
12.19.4.11 int seq64::gui_drawingarea_gtk2::m_current_x [protected]
Current mouse x value.
12.19.4.12 int seq64::gui_drawingarea_gtk2::m_current_y [protected]
```

Provides the x and y value of where the dragging started. Current mouse x-drop value.


12.19.4.13 int seq64::gui_drawingarea_gtk2::m_drop_x [protected]

12.19.4.14 int seq64::gui_drawingarea_gtk2::m_drop_y [protected]

12.20 seq64::gui_palette_gtk2 Class Reference

Implements a stock palette of Gdk::Color elements.

Inheritance diagram for seq64::gui_palette_gtk2:



Public Member Functions

• gui_palette_gtk2 ()

Principal constructor.

~gui_palette_gtk2 ()

Provides a destructor to delete allocated objects.

· const Color & line_color () const

'Getter' function for member m_line_color Provides an experimental way to change some line colors from black to something else.

· const Color & progress_color () const

'Getter' function for member m_progress_color Provides an experimental way to change the progress line color from black to something else.

· const Color & black () const

'Getter' function for member m_black Although these color getters return static values (if so compiled), these colors are used only in the window and drawing-area classes, so no need to make these functions static.

const Color & dark_red () const

'Getter' function for member m_dk_red

· const Color & dark_green () const

'Getter' function for member m_dk_green

const Color & dark_orange () const

'Getter' function for member m_dk_orange

const Color & dark_blue () const

'Getter' function for member m_dk_blue

const Color & dark_magenta () const

'Getter' function for member m_dk_magenta

· const Color & dark cyan () const

'Getter' function for member m_dk_cyan

• const Color & white () const

'Getter' function for member m_white

const Color & grey () const

'Getter' function for member m_grey

const Color & dark_grey () const

'Getter' function for member m dk grey

const Color & light_grey () const

'Getter' function for member m_lt_grey

· const Color & red () const

'Getter' function for member m_red

· const Color & orange () const

'Getter' function for member m_orange

• const Color & yellow () const

'Getter' function for member m yellow

· const Color & green () const

'Getter' function for member m_green

· const Color & blue () const

'Getter' function for member m_blue

const Color & black_paint () const

'Getter' function for member m_blk_paint

• const Color & white_paint () const

'Getter' function for member m_wht_paint

const Color & black_key () const

'Getter' function for member m_blk_key

const Color & white_key () const

'Getter' function for member m_wht_key

• const Color & bg_color () const

'Getter' function for member m_bg_color

void bg_color (const Color &c)

'Setter' function for member m_bg_color

const Color & fg_color () const

'Getter' function for member m_fg_color

• void fg_color (const Color &c)

'Setter' function for member m_fg_color

Static Public Member Functions

static void load inverse palette (bool inverse=true)

Provides an alternate color palette, somewhat constrained by the colors in the font bitmaps.

• static bool is_inverse ()

Indicates if the inverse color palette is loaded.

Protected Types

• typedef Gdk::Color Color

Provides a type for the color object.

Private Attributes

· Color m_line_color

Provides the line color.

• Color m_progress_color

Provides the progress bar color.

Color m_bg_color

The current background color.

Color m_fg_color

The current foreground color.

Static Private Attributes

static bool m_is_inverse

Flags the presense of the inverse color palette.

• static const Color m_black

Provides the black color.

· static const Color m_dk_red

Provides a blood-red color.

• static const Color m_dk_green

Provides a dark green color.

• static const Color m_dk_orange

Provides a dark orange color.

• static const Color m_dk_blue

Provides the dark blue color.

static const Color m_dk_magenta

Provides the dark cyan color.

static const Color m_dk_cyan

Provides the dark cyan color.

· static const Color m red

Provides the red color.

• static const Color m_white

Provides the white color.

• static const Color m_orange

Provides the orange color.

static const Color m_yellow

Provides the yellow color.

· static const Color m green

Provides the green color.

static const Color m_blue

Provides the blue color.

· static Color m grey

Provides the grey color.

· static Color m_dk_grey

Provides the dark grey color.

static Color m_lt_grey

Provides the light grey color.

static Color m blk paint

An invertible black color.

static Color m_wht_paint

An invertible white color.

· static Color m blk key

Provides the color of a black key.

static Color m_wht_key

Provides the color of a white key.

12.20.1 Detailed Description

Note that this class must be derived from Gtk::DrawingArea (or Gtk::Widget) in order to get access to the get_
default_colormap() function used in the constructor.

12.20.2 Member Typedef Documentation

12.20.2.1 typedef Gdk::Color seq64::gui_palette_gtk2::Color [protected]

The following uses are made of each color:

- Black. The background color of armed patterns. The color of most lines in the user interface, including the main grid lines. The default color of progress lines and text.
- White. The default background color of just about everything drawn in the application.
- Grey. The color of minor grid lines and the markers for the currently-selected scale.
- Dark grey. The color of some grid lines, and the background of a queued pattern slot.
- · Light grey. The color of some grid lines.
- Red. The optional color of progress bars.
- · Orange. The fill-in color for selected notes and events.
- · Dark orange. The color of selected event data lines and the color of the selection box for events to be pasted.
- Yellow. The background of the pattern and name slots for empty patterns. The text color for selected empty pattern slots.
- · Green. Not yet used.
- · Blue. Not yet used.
- Dark cyan. The background color of muted patterns currently in edit, or the pattern that contains the original
 data for an imported SMF 0 song. The text color of an unmuted pattern currently in edit. These colors apply
 to the pattern editor and the song editor. The color of the selected background pattern in the song editor.
- · Line color. The generic line color, meant for expansion. Currently black.
- Progress color. The progress line color. Black by default, but can be set to red.
- Background color. The currently-in-use background color. Can vary a lot when a pixmap is being redrawn.
- Foreground color. The currently-in-use foreground color. Can vary a lot when a pixmap is being redrawn.

12.20.3 Constructor & Destructor Documentation

```
12.20.3.1 seq64::gui_palette_gtk2::gui_palette_gtk2 ( )
```

In the constructor one can only allocate colors; get_window() returns 0 because this window has not yet been realized. Also note that the possible color names that can be used are found in /usr/share/X11/rgb.txt.

```
12.20.3.2 seq64::gui_palette_gtk2::~gui_palette_gtk2( )
```

12.20.4 Member Function Documentation

```
12.20.4.1 void seq64::gui_palette_gtk2::load_inverse_palette( bool inverse = true ) [static]
```

Inverse is not a complete inverse. It is more like a "night" mode. However, there are still some bright colors even in this mode. Some colors, such as the selection color (orange) are the same in either mode.

Parameters

	inverse	If true, load the alternate palette. Otherwise, load the default palette.
--	---------	---

```
12.20.4.2 static bool seq64::gui_palette_gtk2::is_inverse( ) [inline], [static]
```

12.20.4.3 const Color& seq64::gui_palette_gtk2::line_color() const [inline]

Might eventually be selectable from the "user" configuration file

12.20.4.4 const Color& seq64::gui_palette_gtk2::progress_color()const [inline]

Now selectable from the "user" configuration file.

```
12.20.4.5 const Color& seq64::gui_palette_gtk2::black( ) const [inline]
```

12.20.4.6 const Color& seq64::gui_palette_gtk2::dark_red() const [inline]

12.20.4.7 const Color& seq64::gui_palette_gtk2::dark_green() const [inline]

12.20.4.8 const Color& seq64::gui_palette_gtk2::dark_orange() const [inline]

12.20.4.9 const Color& seq64::gui_palette_gtk2::dark_blue() const [inline]

12.20.4.10 const Color& seq64::gui_palette_gtk2::dark_magenta() const [inline]

12.20.4.11 const Color& seq64::gui_palette_gtk2::dark_cyan() const [inline]

```
12.20.4.12 const Color& seq64::gui_palette_gtk2::white() const [inline]
12.20.4.13 const Color& seq64::gui_palette_gtk2::grey( ) const [inline]
12.20.4.14 const Color& seq64::gui_palette_gtk2::dark_grey( ) const [inline]
12.20.4.15 const Color& seq64::gui_palette_gtk2::light_grey ( ) const [inline]
12.20.4.16 const Color& seq64::gui_palette_gtk2::red( ) const [inline]
12.20.4.17 const Color& seq64::gui_palette_gtk2::orange( ) const [inline]
12.20.4.18 const Color& seq64::gui_palette_gtk2::yellow( )const [inline]
12.20.4.19 const Color& seq64::gui_palette_gtk2::green( ) const [inline]
12.20.4.20 const Color& seq64::gui_palette_gtk2::blue( ) const [inline]
12.20.4.21 const Color& seq64::gui_palette_gtk2::black_paint( ) const [inline]
12.20.4.22 const Color& seq64::gui_palette_gtk2::white_paint( ) const [inline]
12.20.4.23 const Color& seq64::gui_palette_gtk2::black_key( ) const [inline]
12.20.4.24 const Color& seq64::gui_palette_gtk2::white_key( )const [inline]
12.20.4.25 const Color& seq64::gui_palette_gtk2::bg_color( ) const [inline]
12.20.4.26 void seq64::gui_palette_gtk2::bg_color ( const Color & c ) [inline]
12.20.4.27 const Color& seq64::gui_palette_gtk2::fg_color( ) const [inline]
12.20.4.28 void seq64::gui_palette_gtk2::fg_color( const Color & c ) [inline]
12.20.5 Field Documentation
12.20.5.1 bool seq64::gui_palette_gtk2::m_is_inverse [static], [private]
By default, the inverse color palette is not loaded.
```


```
12.20.5.2 const STATIC_COLOR seq64::gui_palette_gtk2::m_black [static], [private]
12.20.5.3 const STATIC_COLOR seq64::gui_palette_gtk2::m_dk_red [static], [private]
12.20.5.4 const STATIC_COLOR seq64::gui_palette_gtk2::m_dk_green [static], [private]
12.20.5.5 const STATIC_COLOR seq64::gui_palette_gtk2::m_dk_orange [static], [private]
12.20.5.6 const STATIC_COLOR seq64::gui_palette_gtk2::m_dk_blue [static], [private]
12.20.5.7 const STATIC_COLOR seq64::gui_palette_gtk2::m_dk_magenta [static], [private]
12.20.5.8 const STATIC_COLOR seq64::gui_palette_gtk2::m_dk_cyan [static], [private]
12.20.5.9 const STATIC_COLOR seq64::gui_palette_gtk2::m_red [static], [private]
12.20.5.10 const STATIC COLOR seq64::gui palette gtk2::m white [static], [private]
12.20.5.11 const STATIC_COLOR seq64::gui_palette_gtk2::m_orange [static], [private]
12.20.5.12 const STATIC_COLOR seq64::gui_palette_gtk2::m_yellow [static], [private]
12.20.5.13 const STATIC_COLOR seq64::gui_palette_gtk2::m_green [static], [private]
12.20.5.14 const STATIC_COLOR seq64::gui_palette_gtk2::m_blue [static], [private]
12.20.5.15 STATIC_COLOR seq64::gui_palette_gtk2::m_grey [static], [private]
12.20.5.16 STATIC_COLOR seq64::gui_palette_gtk2::m_dk_grey [static], [private]
12.20.5.17 STATIC_COLOR seq64::gui_palette_gtk2::m_lt_grey [static], [private]
12.20.5.18 STATIC_COLOR seq64::gui_palette_gtk2::m_blk_paint [static], [private]
12.20.5.19 STATIC_COLOR seq64::gui_palette_gtk2::m_wht_paint [static], [private]
12.20.5.20 STATIC_COLOR seq64::gui_palette_gtk2::m_blk_key [static], [private]
12.20.5.21 STATIC_COLOR seq64::gui_palette_gtk2::m_wht_key [static], [private]
12.20.5.22 Color seq64::gui_palette_gtk2::m_line_color [private]
12.20.5.23 Color seq64::gui_palette_gtk2::m_progress_color [private]
12.20.5.24 Color seq64::gui_palette_gtk2::m_bg_color [private]
```

12.20.5.25 Color seq64::gui_palette_gtk2::m_fg_color [private]

12.21 seq64::gui_window_gtk2 Class Reference

This class supports a basic interface for Gtk::Window-derived objects.

Inheritance diagram for seq64::gui window gtk2:



Public Member Functions

- gui_window_gtk2 (perform &p, int window_x=0, int window_y=0)
 - Principal constructor, has a reference to the all-important perform object.
- virtual ~gui window gtk2 ()

This rote constructor does nothing.

Protected Member Functions

- perform & perf ()
 - 'Getter' function for member m_mainperf
- · virtual void quit ()

Provides "quit" functionality that WE HAVE OVERLOOKED!!! At some point we need to rectify this situation, probably for the sake of session support.

• int redraw_period_ms () const

'Getter' function for member m_redraw_period_ms

• bool is_realized () const

'Getter' function for member m is realized

· void scroll hadjust (Gtk::Adjustment &hadjust, double step)

This function provides optimization for the on_scroll_event() functions, and should provide support for having the seqedit/seqroll/seqtime/seqdata panes follow the scrollbar, in a future upgrade.

void scroll_vadjust (Gtk::Adjustment &vadjust, double step)

This function is the vertical version of scroll_hadjust().

• void scroll hset (Gtk::Adjustment &hadjust, double value)

This function is the horizontal scroll setter.

• void scroll_vset (Gtk::Adjustment &vadjust, double value)

This function is the vertical scroll setter.

· void on realize ()

This callback function calls the base-class on_realize() function, and sets the m_is_realized flag.

Private Attributes

• perform & m_mainperf

The master object, sort of a sequence buss for all of the sequence.

int m window x

Window sizes.

• int m_window_y

The height of the window.

· int m redraw period ms

Provides the timer period for the eventedit timer, used to determine the rate of redrawing.

· bool m is realized

Indicates if on_realize() has been called.

12.21.1 Constructor & Destructor Documentation

12.21.1.1 seq64::gui_window_gtk2::gui_window_gtk2 (perform & p, int window_x = 0, int window_y = 0)

Note

We've collected the redraw timeouts into a base-class member. Most were valued at c_redraw_ms (40 ms), but mainwind used 25 ms, so beware. We will eventually make this a user-interface parameter.

Parameters

р	Refers to the main performance object.
window←	The width of the window.
_X	
window←	The height of the window.
_y	

12.21.1.2 seq64::gui_window_gtk2::~gui_window_gtk2() [virtual]

12.21.2 Member Function Documentation

```
12.21.2.1 perform& seq64::gui_window_gtk2::perf( ) [inline], [protected]
12.21.2.2 virtual void seq64::gui_window_gtk2::quit( ) [inline], [protected], [virtual]
12.21.2.3 int seq64::gui_window_gtk2::redraw_period_ms( ) const [inline], [protected]
12.21.2.4 bool seq64::gui_window_gtk2::is_realized( ) const [inline], [protected]
12.21.2.5 void seq64::gui_window_gtk2::scroll_hadjust( Gtk::Adjustment & hadjust, double step ) [protected]
```

This function is currently duplicated in the gui_drawingarea_gtk2 and gui_window_gtk2 modules.

Parameters

hadjust	Provides a reference to the adjustment object to be adjusted.
step	Provides the step value to use for adjusting the horizontal scrollbar. If negative, the adjustment is
	leftward. If positive, the adjustment is rightward. It can be the value of
	m_hadjust->get_step_increment(), or provided especially to keep up with the progress bar.

12.21.2.6 void seq64::gui_window_gtk2::scroll_vadjust(Gtk::Adjustment & vadjust, double step) [protected]

Parameters

vadjust	Provides a reference to the adjustment object to be adjusted.
step	Provides the step value to use for adjusting the vertical scrollbar. If greater than 0, the movement is
	downward. If less than zero, the movement is upward.

12.21.2.7 void seq64::gui_window_gtk2::scroll_hset (Gtk::Adjustment & hadjust, double value) [protected]

Parameters

hadjust Provides a reference to the adjustment object to be set. It is clamped as necessary	
value	Provides the value to use for setting the horizontal scrollbar.

12.21.2.8 void seq64::gui_window_gtk2::scroll_vset (Gtk::Adjustment & vadjust, double value) [protected]

Parameters

vadjust Provides a reference to the vertical adjustment object to be set. It is clamped as ne	
value	Provides the value to use for setting the vertical scrollbar.

12.21.2.9 void seq64::gui_window_gtk2::on_realize() [protected]

12.21.3 Field Documentation

```
12.21.3.1 perform& seq64::gui_window_gtk2::m_mainperf [private]
```

And a whole lot more than that.

```
12.21.3.2 int seq64::gui_window_gtk2::m_window_x [private]
```

Could make this constant, but some windows are resizable. The width of the window.

```
12.21.3.3 int seq64::gui_window_gtk2::m_window_y [private]
```

```
12.21.3.4 int seq64::gui_window_gtk2::m_redraw_period_ms [private]
```

This is currently hardwired to 40 ms in Linux, and 20 ms in Windows. Note that mainwind used 25 ms.

```
12.21.3.5 bool seq64::gui_window_gtk2::m_is_realized [private]
```

In some cases, we don't want to draw in objects that haven't yet appeared, otherwise crashes occur.

12.22 seq64::jack_assistant Class Reference

This class provides the performance mode JACK support.

Public Member Functions

jack_assistant (perform &parent, int bpminute=SEQ64_DEFAULT_BPM, int ppqn=SEQ64_USE_DEFAUL
 T_PPQN, int bpm=SEQ64_DEFAULT_BEATS_PER_MEASURE, int beatwidth=SEQ64_DEFAULT_BEAT
 _WIDTH)

This constructor initializes a number of member variables, some of them public!

~jack_assistant ()

The destructor doesn't need to do anything yet.

· perform & parent ()

'Getter' function for member m_jack_parent Needed for external callbacks.

• bool is_running () const

'Getter' function for member m_jack_running

bool is_master () const

'Getter' function for member m_jack_master

• int get_ppqn () const

'Getter' function for member m_ppqn

int get_beat_width () const

'Getter' function for member m_beat_width

· void set beat width (int bw)

'Setter' function for member m_beat_width

• int get_beats_per_measure () const

'Getter' function for member m_beats_per_measure

void set_beats_per_measure (int bpm)

'Setter' function for member m beats per measure

• int get_beats_per_minute () const

'Getter' function for member m_beats_per_minute

void set_beats_per_minute (int bpminute)

'Setter' function for member m_beats_per_minute For the future, changing the BPM (beats/minute) internally.

jack_transport_state_t transport_state () const

'Getter' function for member m_jack_transport_state

• bool init ()

Initializes JACK support.

· bool deinit ()

Tears down the JACK infrastructure.

• bool session_event ()

Writes the MIDI file named "< jack session dir>-file.mid" using a midifile object, quits if told to by JACK, and can free the JACK session event.

• void start ()

If JACK is supported, starts the JACK transport.

void stop ()

If JACK is supported, stops the JACK transport.

void position (bool to_left_tick, bool relocate=false)

If JACK is supported and running, sets the position of the transport to the new frame number, frame 0.

bool output (jack_scratchpad &pad)

Performance output function for JACK, called by the perform function of the same name.

void set_ppqn (int ppqn)

'Setter' function for member m_ppqn For the future, changing the PPQN internally.

double get_jack_tick () const

'Getter' function for member m_jack_tick

const jack_position_t & get_jack_pos () const

'Getter' function for member m_jack_pos

• jack_client_t * client () const

'Getter' function for member m_jack_client

· const std::string & client_name () const

'Getter' function for member m_jack_client_name

const std::string & client_uuid () const

'Getter' function for member m_jack_client_uuid

Private Member Functions

void set_jack_running (bool flag)

'Setter' function for member m_jack_running

• double tick_multiplier () const

Convenience function for internal use.

bool info message (const std::string &msg)

Common-code for console messages.

bool error_message (const std::string &msg)

Common-code for error messages.

jack client t * client open (const std::string &clientname)

A more full-featured initialization for a JACK client, which is meant to be called by the init() function.

• void get_jack_client_info ()

Tries to obtain the best information on the JACK client and the UUID assigned to this client.

void show_statuses (unsigned bits)

Loops through the full set of JACK bits, showing the information for any bits that are set in the given parameter.

void show_position (const jack_position_t &pos) const

Shows a one-line summary of a JACK position structure.

int sync (jack_transport_state_t state=(jack_transport_state_t)(-1))

A helper function for syncing up with JACK parameters.

void set_position (midipulse currenttick)

Provides the code that was effectively commented out in the perform::position_jack() function.

Private Attributes

perform & m_jack_parent

Provides the perform object that needs this JACK assistant/scratchpad class.

jack_client_t * m_jack_client

Provides a handle into JACK, so that the application, as a JACK client, can issue commands and retrieve status information from JACK.

std::string m jack client name

A new member to hold the actual name of the client assigned by JACK.

• std::string m_jack_client_uuid

A new member to hold the actual UUID of the client assigned by JACK.

• jack_nframes_t m_jack_frame_current

Holds the current frame number obtained from JACK transport, via a call to jack_get_current_transport_frame().

jack_nframes_t m_jack_frame_last

Holds the last frame number we got from JACK, so that progress can be tracked.

• jack_position_t m_jack_pos

Provides positioning information on JACK playback.

• jack_transport_state_t m_jack_transport_state

Holds the JACK transport state.

• jack_transport_state_t m_jack_transport_state_last

Holds the last JACK transport state.

double m_jack_tick

The tick/pulse value derived from the current frame number, the ticks/beat value, the beats/minute value, and the frame rate.

jack_session_event_t * m_jsession_ev

Provides a kind of handle to the JACK session manager.

bool m_jack_running

Indicates if JACK Sync has been enabled successfully.

bool m_jack_master

Indicates if JACK Sync has been enabled successfully, with the application running as JACK Master.

int m_ppqn

Holds the global PPQN value for the Sequencer64 session.

• int m_beats_per_measure

Holds the song's beats/measure value for using in setting JACK position.

int m_beat_width

Holds the song's beat width value (denominator of the time signature) for using in setting JACK position.

• int m_beats_per_minute

Holds the song's beats/minute (BPM) value for using in setting JACK position.

Static Private Attributes

• static jack_status_pair_t sm_status_pairs []

Pairs the JACK status bits with human-readable descriptions of each one.

Friends

- int jack_process_callback (jack_nframes_t nframes, void *arg)
- void jack_shutdown_callback (void *arg)

This callback is to shut down JACK by clearing the jack_assistant :: m_jack_running flag.

 $\bullet \ \ int \ jack_sync_callback \ (jack_transport_state_t \ state, \ jack_position_t \ *pos, \ void \ *arg)\\$

Global functions for JACK support and JACK sessions.

void jack_timebase_callback (jack_transport_state_t state, jack_nframes_t nframes, jack_position_t *pos, int new_pos, void *arg)

The JACK timebase function defined here sets the JACK position structure.

- long get_current_jack_position (void *arg)
- void jack_session_callback (jack_session_event_t *ev, void *arg)

Set the m_jsession_ev (event) value of the perform object.

12.22.1 Constructor & Destructor Documentation

12.22.1.1 seq64::jack_assistant::jack_assistant (perform & parent, int bpminute = SEQ64_DEFAULT_BPM, int ppqn = SEQ64_USE_DEFAULT_PPQN, int bpm = SEQ64_DEFAULT_BEATS_PER_MEASURE, int beatwidth = SEQ64_DEFAULT_BEAT_WIDTH)

Note that the perform object currently calls jack_assistant::init(), but that call could be made here instead.

Parameters

parent	Provides a reference to the main perform object that needs to control JACK event.
bpminute The beats/minute to set up JACK to use (applies to Master setup).	
ppqn The parts-per-quarter-note setting in force for the present tune.	
bpm	The beats/measure (time signature numerator) in force for the present tune.
beatwidth	The beat-width (time signature denominator) in force for the present tune.

```
12.22.1.2 seq64::jack_assistant::~jack_assistant()
```

The perform object currently calls jack_assistant::deinit(), but that call could be made here instead.

12.22.2 Member Function Documentation

```
12.22.2.1 perform& seq64::jack_assistant::parent() [inline]
```

12.22.2.2 bool seq64::jack_assistant::is_running() const [inline]

```
12.22.2.3 bool seq64::jack_assistant::is_master( ) const [inline]
12.22.2.4 int seq64::jack_assistant::get_ppqn( ) const [inline]
12.22.2.5 int seq64::jack_assistant::get_beat_width( ) const [inline]
12.22.2.6 void seq64::jack_assistant::set_beat_width( int bw ) [inline]
```

bw Provides the beat-width (denominator of the time signature) value to set.

```
12.22.2.7 int seq64::jack_assistant::get_beats_per_measure( ) const [inline]
```

12.22.2.8 void seq64::jack_assistant::set_beats_per_measure(int bpm) [inline]

Parameters

bpm Provides the beats/measure (numerator of the time signature) value to set.

```
12.22.2.9 int seq64::jack_assistant::get_beats_per_minute() const [inline]
```

12.22.2.10 void seq64::jack_assistant::set_beats_per_minute(int bpminute) [inline]

We should consider adding validation. However, perform::set_beats_per_minute() does validate already.

Parameters

bpminute	Provides the beats/minute value to set.

```
12.22.2.11 jack_transport_state_t seq64::jack_assistant::transport_state( ) const [inline]
```

12.22.2.12 bool seg64::jack_assistant::init()

Then we become a new client of the JACK server.

A sync callback is needed for polling of slow-sync clients. But seq24/sequencer64 are not slow-sync clients. We don't really need to be a slow-sync client, as far as we can tell. We can't get JACK working exactly the way it does in seq24 without the callback in place. Plus, it does things important to the setup of JACK. So now this setup is permanent.

Jack transport settings:

```
There are three settings: On, Master, and Master Conditional. Currently, they can all be selected in the user-interface's File / Options / JACK/LASH page. We really want only the proper combinations to be set, for clarity (the user-interface now takes care of this. We need to initialize if any of them are set, and the rc_settings::with_jack() function tells us that.
```

jack_set_process_callback() patch:

```
Implemented first patch from freddix/seq24 GitHub project, to fix JACK transport. One line of code. Well, we added some error-checking. :-) Found some old notes on the Web the this patch really only works (to prevent seq24 freeze) if seq24 is set as JACK Master, or if another client application, such as Qtractor, is running as JACK Master (and then seq24 will apparently follow it).
```

STAZED: The call to jack_timebase_callback() to supply jack with BBT, etc would occasionally fail when the *pos information had zero or some garbage in the pos.frame_rate variable. This would occur when there was a rapid change of frame position by another client... i.e. qjackctl. From the jack API:

"pos address of the position structure for the next cycle; pos->frame will be its frame number. If new_pos is FALSE, this structure contains extended position information from the current cycle. If TRUE, it contains whatever was set by the requester. The timebase_callback's task is to update the extended information here."

The "If TRUE" line seems to be the issue. It seems that qjackctl does not always set pos.frame_rate so we get garbage and some strange BBT calculations that display in qjackctl. So we need to set it here and just use m_\circ
jack frame rate for calculations instead of pos.frame rate.

Returns

Returns true if JACK is now considered to be running (or if it was already running.)

```
12.22.2.13 bool seq64::jack_assistant::deinit()
```

Returns

Returns the value of m jack running, which should be false.

```
12.22.2.14 bool seq64::jack_assistant::session_event()
```

ca 2015-07-24 Just a note: The OMA (OpenMandrivaAssociation) patch was already applied to seq24 v.0.9.2. It put quotes around the –file argument. However, the –file option doesn't work, so let's change that line.

```
sequencer64 --file \"${SESSION_DIR}file.mid\" --jack_session_uuid
```

Why are we using a Glib::ustring here? Convenience. But with C++11, we could use a lexical_cast<>. No more ustring, baby! It doesn't really matter; this function can call Gtk::Main::quit(), via the parent's gui().quit() function.

Returns

Always returns false.

```
12.22.2.15 void seq64::jack_assistant::start()
```

This function assumes that m_jack_client is not null, if m_jack_running is true.

Found this note in the Hydrogen code:

```
When jack_transport_start() is called, it takes effect from the next processing cycle. The location info from the timebase_master, if there is one, will not be available until the _next_ next cycle. The code must therefore wait one cycle before syncing up with timebase master.
```

```
12.22.2.16 void seq64::jack_assistant::stop()
```

This function assumes that m_jack_client is not null, if m_jack_running is true.

```
12.22.2.17 void seq64::jack_assistant::position ( bool to_left_tick, bool relocate = false )
```

This new position takes effect in two process cycles. If there are slow-sync clients and the transport is already rolling, it will enter the JackTransportStarting state and begin invoking their sync_callbacks until ready. This function is realtime-safe.

```
http://jackaudio.org/files/docs/html/transport-design.html
```

This position() function is called via perform::position_jack() in the mainwnd, perfedit, perfroll, and seqroll graphical user-interface support objects.

The code that was disabled sets the current tick to 0 or, if state was true, to the leftmost tick (which is probably the position of the L marker). The current tick is then converted to a frame number, and then we locate the transport to that position. We're going to enable this code, but make it dependent on a new boolean parameter that defaults to false, in anticipation of trying it out later.

These repositions reset the progress bars. We don't always want that, it should be an option. TODO.

jack_transport_reposition():

```
Requests a new transport position. The new position takes effect in two process cycles. If there are slow-sync clients and the transport is already rolling, it will enter the JackTransportStarting state and begin invoking their sync_callbacks until ready. This function is realtime-safe.
```

It's pos parameter provides the requested new transport position. Fill pos->valid to specify which fields should be taken into account. If you mark a set of fields as valid, you are expected to fill them all. Note that "frame" is always assumed, and generally needs to be set:

```
http://comments.gmane.org/gmane.comp.audio.jackit/18705
```

Returns 0 if a valid request, ${\tt EINVAL}$ if the position structure is rejected.

Stazed:

The jack_frame calculation is all that is needed to change JACK position The BBT calc can be sent but will be overridden by the first call to jack_timebase_callback() of any Master set. If no Master is set, then the BBT will display the new position but will not change even if the transport is rolling. There is no need to send BBT on position change - the fact that the function jack_transport_locate() exists and only uses the frame position is proof that BBT is not needed! Upon further reflection, why not send BBT? Because other programs do not... let's follow convention. The below calculation for jack_transport_locate(), works, is simpler and does not send BBT. The calculation for jack_transport_reposition() will be commented out again. The BBT call to jack_BBT_position() is not necessary to change jack position!

Warning

A lot of this code is effectively disabled by an early return statement.

to_left_tick	If true, the current tick is set to the leftmost tick, instead of the 0th tick. Now used, but only if
	relocate is true. One question is, do we want to perform this function if rc().with_jack_transport()
	is true? Seems like we should be able to do it only if m_jack_master is true.
relocate	If true (it defaults to false), then we allow the relocation of the JACK transport to the current_tick or the left tick, rather than to frame 0. EXPERIMENTAL, enables dead code from seq24. Seems to work if set to true when we are the JACK Master. Enabling this code makes "klick -j -P" work, after a fashion. It clicks, but at a way too rapid rate.

12.22.2.18 bool seq64::jack_assistant::output (jack_scratchpad & pad)

This code comes from perform::output func() from seq24.

Note

Follow up on this note found "out there": "Maybe I'm wrong but if I understood correctly, recent jack1 transport no longer goes into Jack_Transport_Starting state before going to Jack_Transport_Rolling (this was deliberately dropped), but seq24 currently needs this to start off with JACK transport." On the other hand, some people have no issues. This may have been due to the lack of m_jack_pos initialization.

Stazed:

Another note about JACK.... If another JACK client is supplying tempo/BBT info that is different from seq42 (as Master), the perfroll grid will be incorrect. Perfroll uses internal temp/BBT and cannot update on the fly. Even if seq42 could support tempo/BBT changes, all info would have to be available before the transport start, to work. For this reason, the tempo/BBT info will be plugged from the seq42 internal settings here... always. This is the method used by probably all other JACK clients with some sort of time-line. The JACK API indicates that BBT is optional and AFIK, other sequencers only use frame & frame_rate from JACK for internal calculations. The tempo and BBT info is always internal. Also, if there is no Master set, then we would need to plug it here to follow the JACK frame anyways.

Parameters

pad	Provide a JACK scratchpad for sharing certain items between the perform object and the jack_assistant
	object.

Returns

Returns true if JACK is running.

12.22.2.19 void seq64::jack_assistant::set_ppqn (int ppqn) [inline]

We should consider adding validation. But it is used by perform.

ppqn	Provides the PPQN value to set.
------	---------------------------------

```
12.22.2.21 const jack_position_t& seq64::jack_assistant::get_jack_pos() const [inline]

12.22.2.22 jack_client_t* seq64::jack_assistant::client() const [inline]

12.22.2.23 const std::string& seq64::jack_assistant::client_name() const [inline]

12.22.2.24 const std::string& seq64::jack_assistant::client_uuid() const [inline]

12.22.2.25 void seq64::jack_assistant::set_jack_running(bool flag) [inline], [private]
```

flag | Provides the is-running value to set.

12.22.2.26 double seq64::jack_assistant::tick_multiplier() const [inline], [private]

Should we change 4.0 to a member value? What does it mean?

Returns

Returns the multiplier to convert a JACK tick value according to the PPQN, ticks/beat, and beat-type settings.

12.22.2.27 bool seq64::jack_assistant::info_message (const std::string & msg) [private]

Adds markers and a newline.

Parameters

msg The message to print, sans the newline.

Returns

Returns true.

12.22.2.28 bool seq64::jack_assistant::error_message (const std::string & msg) [private]

Adds markers, and sets m_jack_running to false.

Parameters

msg The message to print, sans the newline.

Returns

Returns false for convenience/brevity in setting function return values.

12.22.2.29 jack_client_t * seq64::jack_assistant::client_open(const std::string & clientname) [private]

Status bits for jack status t return pointer:

JackNameNotUnique means that the client name was not unique. With JackUseExactName, this is fatal. Otherwise, the name was modified by appending a dash and a two-digit number in the range "-01" to "-99". The jack_get_client_name() function returns the exact string used. If the specified client_name plus these extra characters would be too long, the open fails instead.

JackServerStarted means that the JACK server was started as a result of this operation. Otherwise, it was running already. In either case the caller is now connected to jackd, so there is no race condition. When the server shuts down, the client will find out.

JackOpenOptions:

```
JackSessionID | JackServerName | JackNoStartServer | JackUseExactName
Only the first is used at present.
```

Parameters

clientname

Provides the name of the client, used in the call to jack_client_open(). By default, this name is the macro SEQ64_PACKAGE (i.e. "sequencer64"). The name scope is local to each server. Unless forbidden by the JackUseExactName option, the server will modify this name to create a unique variant, if needed.

Returns

Returns a pointer to the JACK client if JACK has opened the client connection successfully. Otherwise, a null pointer is returned.

```
12.22.2.30 void seq64::jack_assistant::get_jack_client_info() [private]
```

Sets m jack client name and m jack client info as side-effects.

```
12.22.2.31 void seq64::jack_assistant::show_statuses ( unsigned bits ) [private]
```

For reference, here are the enumeration values from /usr/include/jack/types.h:

```
JackFailure = 0x01

JackInvalidOption = 0x02

JackNameNotUnique = 0x04

JackServerStarted = 0x08

JackServerFailed = 0x10

JackServerError = 0x20
```

```
JackNoSuchClient = 0x40

JackLoadFailure = 0x80

JackInitFailure = 0x100

JackShmFailure = 0x200

JackVersionError = 0x400

JackBackendError = 0x800

JackClientZombie = 0x1000
```

Parameters

bits The mask of the bits to be shown in the output.

12.22.2.32 void seq64::jack_assistant::show_position(const jack_position_t & pos) const [private]

This function is meant for experimenting and learning.

The fields of this structure are as follows. Only the fields we care about are shown.

```
iack nframes t
                    frame_rate:
                                  current frame rate (per second)
                    frame:
+ walid:
   jack_nframes_t
                                  frame number, always present
   jack_position_bits_t valid:
                                  which other fields are valid
JackPositionBBT:
   int32 t
                                  current bar
                   bar:
   int32_t
                   beat:
                                 current beat-within-bar
   int32_t
                   tick:
bar_start_tick
                                  current tick-within-beat
   double
                    beats_per_bar: time signature "numerator"
                                  time signature "denominator"
   float.
                   beat_type:
   double
                     ticks_per_beat
   double
                    beats_per_minute
JackBBTFrameOffset:
   jack_nframes_t
                     bbt_offset;
                                  frame offset for the BBT fields
Only the most "important" and time-varying fields are shown. The format
output is brief and inscrutable unless you read this format example:
   nnnnn frame B:B:T N/D TPB BPM BBT
                   | | | ----- bbt_offset (frame), even if invalid
                          -----beats_per_minute
                   ----- ticks_per_beat (PPQN * 10?)
                   | ----- beat_type (denominator)
                   ----- beats_per_bar (numerator)
                  ----- bar : beat : tick
           ----- frame (number)
        ----- the "valid" bits
The "valid" field is shown as bits in the same bit order as shown here, but
represented as a five-character string, "nnnnn", n = 0 or 1:
   JackVideoFrameOffset = 0x100
   JackAudioVideoRatio = 0x080
   JackBBTFrameOffset = 0x040
   JackPositionTimecode = 0x020
   JackPositionBBT
                     = 0 \times 010
```

We care most about nnnn = "00101" in our experiments (the most common

measurements... we truncate them to integers. Change the output format if

output will be "00001"). And we don't worry about non-integer

you want to play with non-Western timings.

Parameters

pos	The JACK position structure to dump.
-----	--------------------------------------

Sequencer64 is not a slow-sync client (and Stazed support doesn't use it), so that callback is not really needed, but we probably need this sub-function here to start out with the right values for interacting with JACK.

Note the call to jack_transport_query(). This call is *not* is seq24, but seems to be needed in sequencer64 because we put m_jack_pos in the initializer list, which sets all its fields to 0. Seq24 accesses m_jack_pos before it ever gets set, but its fields have values. These values are bogus, but are consistent from run to run on my computer, and allow seq24 to follow another JACK Master, on some computers. It explains why people had different experiences with JACK sync.

If we explicity call jack_transport_query() here, without changing the *state* parameter, then sequencer64 also can follow another JACK Master. (CURRENTLY BUGGY!)

Note that we should consider massaging the following jack_position_t members to set them to 0 (or 0.0) if less than 1.0 or 0.5:

```
- bar_start_tick
- ticks_per_beat
- beats_per_minute
- frame_time
- next_time
- audio_frames_per_video_frame
```

Also, why does bbt_offset start at 2128362496?

Parameters

```
state The JACK transport state to be set.
```

12.22.2.34 void seq64::jack assistant::set position (midipulse currenttick) [private]

We might be able to use it in other functions.

Computing the BBT information from the frame number is relatively simple here, but would become complex if we supported tempo or time signature changes at specific locations in the transport timeline.

```
ticks * 10 = jack ticks;
jack ticks / ticks per beat = num beats;
num beats / beats per minute = num minutes
num minutes * 60 = num seconds
num secords * frame_rate = frame
```

Parameters

currenttick	Provides the current position to be set.
-------------	--

12.22.3 Friends And Related Function Documentation

```
12.22.3.1 int jack process callback (jack nframes t nframes, void * arg ) [friend]
```

```
12.22.3.2 void jack_shutdown_callback( void * arg ) [friend]
```

Parameters

arg	Points to the jack_assistant in charge of JACK support for the perform object.
-----	--

```
12.22.3.3 int jack_sync_callback ( jack_transport_state_t state, jack_position_t * pos, void * arg ) [friend]
```

This JACK synchronization callback informs the specified perform object of the current state and parameters of JACK.

The transport state will be:

- JackTransportStopped when a new position is requested.
- JackTransportStarting when the transport is waiting to start.
- JackTransportRolling when the timeout has expired, and the position is now a moving target.

This is the slow-sync callback, which stazed replaces with jack process callback().

Parameters

state	The JACK Transport state.
pos	The JACK position value.
arg	The pointer to the jack_assistant object. Currently not checked for nullity, nor dynamic-casted.

Returns

Returns 1 if the function works, and 0 if something was wrong.

```
12.22.3.4 void jack_timebase_callback ( jack_transport_state_t state, jack_nframes_t nframes, jack_position_t * pos, int new_pos, void * arg ) [friend]
```

The original version of the function worked properly with Hydrogen, but not with Klick. The new code seems to work with both. More testing and clarification is needed. This new code was "discovered" in the source-code for the "SooperLooper" project:

```
http://essej.net/sooperlooper/
```

The first difference with the new code is that it handles the case where the JACK position is moved (new_pos == true). If this is true, and the JackPositionBBT bit is off in pos->valid, then the new BBT value is set.

The seconds set of differences are in the "else" clause. In the new code, it is very simple: calculate the new tick value, back it off by the number of ticks in a beat, and perhaps go to the first beat of the next bar.

In the old code (complex!), the simple BBT adjustment is always made. This changes (perhaps) the beats_per_bar, beat_type, etc. We need to make these settings use the actual global values for beats set for Sequencer64. Then, if transitioning from JackTransportStarting to JackTransportRolling (instead of checking new_pos!), the BBT values (bar, beat, and tick) are finally adjusted. Here are the steps, with old and new steps noted:

- -# Calculate the "delta" ticks based on the current frame, the ticks_per_beat, the beats_per_minute, and the frame_rate. The old code saves this in a local, the new code assigns it to pos->tick.
- -# Old code: save this delta as a positive value.
- -# Figure out the settings and modify bar, beat, tick, and bar_start_tick. The old and new code seem to have the same intent, but it seems like the new code is faster and also correct.
 - Old code: Calculations are made by division and mod operations.
 - New code: Calculations are made by increments and decrements in a while loop.

Stazed:

The call to jack_timebase_callback() to supply JACK with BBT, etc. would occasionally fail when the pos information had zero or some garbage in the pos.frame_rate variable. This would occur when there was a rapid change of frame position by another client... i.e. qjackctl. From the JACK API:

pos address of the position structure for the next cycle; pos->frame will be its frame number. If new_pos is FALSE, this structure contains extended position information from the current cycle. If TRUE, it contains whatever was set by the requester. The timebase_callback's task is to update the extended information here."

The "If TRUE" line seems to be the issue. It seems that qjackctl does not always set pos.frame_rate so we get garbage and some strange BBT calculations that display in qjackctl. So we need to set it here and just use m_jack_frame_rate for calculations instead of pos.frame_rate.

Parameters

state	Indicates the current state of JACK transport.
nframes	The number of JACK frames in the current time period.
pos	Provides the position structure to be filled in, the address of the position structure for the next cycle; pos->frame will be its frame number. If new_pos is FALSE, this structure contains extended position information from the current cycle. If TRUE, it contains whatever was set by the requester. The timebase_callback's task is to update the extended information here.
new_pos	TRUE (non-zero) for a newly requested pos, or for the first cycle after the timebase_callback is defined. This is usually 0 in Sequencer64 at present, and 1 if one, say, presses "rewind" in qjackctl.
arg	Provides the jack_assistant pointer, currently unchecked for nullity.

```
12.22.3.5 long get_current_jack_position ( void * arg ) [friend]
```

```
12.22.3.6 void jack_session_callback( jack_session_event_t * ev, void * arg ) [friend]
```

Glib is then used to connect in perform::jack_session_event(). However, the perform object's GUI-support interface is used instead of the following, so that the libseq64 library can be independent of a specific GUI framework:

```
Glib::signal_idle().
    connect(sigc::mem_fun(*jack, &jack_assistant::session_event));
```

Parameters

ev	The JACK event to be set.	Ì
arg	The pointer to the jack_assistant object. Currently not checked for nullity.	ŀ
Generated by Doxygen		1

12.22.4 Field Documentation

```
12.22.4.1 jack_status_pair_t seq64::jack_assistant::sm_status_pairs [static], [private]
```

Provides a list of JACK status bits, and a brief string to explain the status bit.

Terminated by a 0 value and an empty string.

```
12.22.4.2 perform& seq64::jack_assistant::m_jack_parent [private]
```

```
12.22.4.3 jack_client_t* seq64::jack_assistant::m_jack_client [private]
```

12.22.4.4 std::string seq64::jack_assistant::m_jack_client_name [private]

We might show this in the user-interface at some point.

```
12.22.4.5 std::string seq64::jack_assistant::m_jack_client_uuid [private]
```

We might show this in the user-interface at some point.

```
12.22.4.6 jack_nframes_t seq64::jack_assistant::m_jack_frame_current [private]
```

```
12.22.4.7 jack_nframes_t seq64::jack_assistant::m_jack_frame_last [private]
```

Also used in incrementing m jack tick.

```
12.22.4.8 jack_position_t seq64::jack_assistant::m_jack_pos [private]
```

This structure is filled via a call to jack_transport_query(). It holds, among other items, the frame rate (often 48000), the ticks/beat, and the beats/minute.

```
12.22.4.9 jack_transport_state_t seq64::jack_assistant::m_jack_transport_state [private]
```

Common values are JackTransportStopped, JackTransportRolling, and JackTransportLooping.

```
12.22.4.10 jack_transport_state_t seq64::jack_assistant::m_jack_transport_state_last [private]
```

12.22.4.11 double seq64::jack_assistant::m_jack_tick [private]

12.22.4.12 jack_session_event_t* seq64::jack_assistant::m_jsession_ev [private]

Used in the session_event() function.

```
12.22.4.14 bool seq64::jack_assistant::m_jack_running [private]

12.22.4.15 int seq64::jack_assistant::m_ppqn [private]

It is used for calculating ticks/beat (pulses/beat) and for setting the tick position.

12.22.4.16 int seq64::jack_assistant::m_beats_per_measure [private]

12.22.4.17 int seq64::jack_assistant::m_beat_width [private]

12.22.4.18 int seq64::jack_assistant::m_beats_per_minute [private]
```

12.23 seq64::jack_scratchpad Class Reference

Provide a temporary structure for passing data and results between a perform and jack_assistant object.

Data Fields

- · double is current tick
 - Holds current location.
- double js_total_tick

Current location ignoring L/R.

• double js_clock_tick

Identical to js_total_tick.

· bool js_jack_stopped

Flags perform::inner_stop().

bool js_dumping

Non-JACK playback in progress?

· bool js_init_clock

We now have a good JACK lock.

· bool js_looping

seqedit loop button is active.

bool js_playback_mode

Song mode (versus live mode).

• double js_ticks_converted_last

Keeps track of position?

12.23.1 Detailed Description

The jack_assistant class already has access to the members of perform, but it needs access to and modification of "local" variables in perform::output_func(). This scratchpad is useful even if JACK support is not enabled.

12.23.2 Field Documentation

12.23.2.2	double seq64::jack_scratchpad::js_total_tick

12.23.2.1 double seq64::jack_scratchpad::js_current_tick

12.23.2.3 double seq64::jack_scratchpad::js_clock_tick

12.23.2.4 bool seq64::jack_scratchpad::js_jack_stopped

12.23.2.5 bool seq64::jack_scratchpad::js_dumping

12.23.2.6 bool seq64::jack_scratchpad::js_init_clock

12.23.2.7 bool seq64::jack_scratchpad::js_looping

12.23.2.8 bool seq64::jack_scratchpad::js_playback_mode

12.23.2.9 double seq64::jack_scratchpad::js_ticks_converted_last

12.24 seq64::jack_status_pair_t Struct Reference

Provides an internal type to make it easier to display a specific and accurate human-readable message when a JACK operation fails.

Data Fields

unsigned jf_bit

Holds one of the bit-values from jack_status_t, which is defined as an "enum JackStatus" type.

std::string jf_meaning

Holds a textual description of the corresponding status bit.

12.24.1 Field Documentation

12.24.1.1 unsigned seq64::jack_status_pair_t::jf_bit

12.24.1.2 std::string seq64::jack_status_pair_t::jf_meaning

12.25 seq64::keybindentry Class Reference

Class for management of application key-bindings.

Inherits Entry.

Public Member Functions

keybindentry (type t, unsigned int *location_to_write=nullptr, perform *p=nullptr, long s=0)

This constructor initializes the member with values dependent on the value type provided in the first parameter.

void set (unsigned int val)

Gets the key name from the integer value; if there is one, then it is printed into a temporary buffer, otherwise the value is printed into that buffer as is.

virtual bool on_key_press_event (GdkEventKey *event)

Handles a key press by calling set() with the event's key value.

Private Types

Private Attributes

unsigned int * m_key

Points to the value of the key that is part of this key-binding.

• type m_type

Stores the type of key-binding.

• perform * m_perf

Stores an optional pointer to a perform object.

• long m slot

Provides an index into a set of group-keys or event-keys.

Friends

class options

12.25.1 Member Enumeration Documentation

```
12.25.1.1 enum seq64::keybindentry::type [private]
```

Enumerator

location Used for handling a keystroke made while a keyboard-options field is active, for selecting a key via the keyboard, and binding to pattern/sequence boxes, we think. It is used in the options class to associate a key with the binding.

events Used for binding to events.

groups Used for binding to groups.

12.25.2 Constructor & Destructor Documentation

```
12.25.2.1 seq64::keybindentry::keybindentry ( type t, unsigned int * location_to_write = nullptr, perform * p = nullptr, long s = 0 )
```

Usage In options, a pointer to a new key-binding entry is managed by calling keybindentry (keybindentry ::location, &perf→keyname).

Parameters

t	Provides the type of key-binding: location, events, or groups.
location_to_write	The location that holds the value of the key associated with the key-binding. The default value of this parameter is the null pointer.
р	Points to the performance object used with this key-binding. The default value of this parameter is the null pointer.
S	Provides the slot value for this key-binding. The default value of this parameter is zero.

12.25.3 Member Function Documentation

12.25.3.1 void seq64::keybindentry::set (unsigned int val)

Then we call set_text(buf). The set_width_char() function is then called.

12.25.3.2 bool seq64::keybindentry::on_key_press_event (GdkEventKey * event) [virtual]

This value is used to set the event or key depending on the value of m_type.

Parameters

event	Provides the key-press event.
-------	-------------------------------

Returns

Returns the result of the call to Entry::on_key_press_event().

12.25.4 Friends And Related Function Documentation

12.25.4.1 friend class options [friend]

12.25.5 Field Documentation

12.25.5.1 unsigned int* seq64::keybindentry::m_key [private]

Not yet sure by the address of this key value is needed. It can be a null pointer, as well.

12.25.5.2 type seq64::**keybindentry**::**m_type** [private]

12.25.5.3 perform* seq64::keybindentry::m_perf [private]


12.25.5.4 long seq64::keybindentry::m_slot [private]

(This item should be changed to unsigned int, though.)

12.26 seq64::keys_perform Class Reference

This class supports the performance mode.

Inheritance diagram for seq64::keys_perform:



Public Member Functions

• keys_perform ()

This construction initializes a vast number of member variables, some of them public!

virtual ~keys_perform ()

The destructor sets some running flags to false, signals this condition, then joins the input and output threads if the were launched.

void set_keys (const keys_perform_transfer &kpt)

Copies fields from the transfer structure in this object.

void get_keys (keys_perform_transfer &kpt)

Copies fields from this object into the transfer structure.

unsigned int bpm up () const

'Getter' function for member m_key_bpm_up

void bpm_up (unsigned int x)

'Setter' function for member m_key_bpm_up

unsigned int bpm_dn () const

'Getter' function for member m_key_bpm_dn

void bpm_dn (unsigned int x)

'Setter' function for member m_key_bpm_dn

unsigned int replace () const

'Getter' function for member m_key_replace

void replace (unsigned int x)

'Setter' function for member m_key_replace

• unsigned int queue () const

'Getter' function for member m_key_queue

• void queue (unsigned int x)

'Setter' function for member m_key_queue

• unsigned int keep_queue () const

'Getter' function for member m_key_keep_queue

void keep queue (unsigned int x)

'Setter' function for member m_key_keep_queue

unsigned int snapshot_1 () const

'Getter' function for member m key snapshot 1

void snapshot_1 (unsigned int x)

'Setter' function for member m_key_snapshot_1

• unsigned int snapshot_2 () const

'Getter' function for member m_key_snapshot_2

void snapshot_2 (unsigned int x)

'Setter' function for member m_key_snapshot_2

• unsigned int screenset_up () const

'Getter' function for member m_key_screenset_up

void screenset_up (unsigned int x)

 ${\it 'Setter' function for member m_key_screenset_up}$

• unsigned int screenset dn () const

'Getter' function for member m_key_screenset_dn

void screenset_dn (unsigned int x)

 ${\it 'Setter' function for member m_key_screenset_dn}$

unsigned int set_playing_screenset () const

'Getter' function for member m_key_playing_screenset

void set_playing_screenset (unsigned int x)

'Setter' function for member m_key_playing_screenset

• unsigned int group on () const

'Getter' function for member m_key_group_on

void group_on (unsigned int x)

'Setter' function for member m_key_group_on

unsigned int group_off () const

'Getter' function for member m_key_group_off

void group_off (unsigned int x)

'Setter' function for member m_key_group_off

• unsigned int group_learn () const

'Getter' function for member m_key_group_learn

void group_learn (unsigned int x)

'Setter' function for member m_key_group_learn

• unsigned int start () const

'Getter' function for member m key start

void start (unsigned int x)

'Setter' function for member m_key_start

• unsigned int pause () const

'Getter' function for member m_key_pause

void pause (unsigned int x)

'Setter' function for member m_key_pause

unsigned int pattern_edit () const

'Getter' function for member m_key_pattern_edit

void pattern edit (unsigned int x)

'Setter' function for member m_key_pattern_edit

unsigned int event_edit () const

'Getter' function for member m key event edit

void event_edit (unsigned int x)

'Setter' function for member m_key_event_edit

• unsigned int stop () const

'Getter' function for member m_key_stop

void stop (unsigned int x)

'Setter' function for member m_key_stop

· bool show ui sequence key () const

'Getter' function for member m_key_show_ui_sequency_key

void show_ui_sequence_key (bool flag)

'Setter' function for member m_key_show_ui_sequency_key

bool show_ui_sequence_number () const

'Getter' function for member m_key_show_ui_sequency_number

void show_ui_sequence_number (bool flag)

'Setter' function for member m_key_show_ui_sequency_key

SlotMap & get_key_events ()

'Getter' function for member m_key_events

SlotMap & get_key_groups ()

'Getter' function for member m_key_groups

• RevSlotMap & get_key_events_rev ()

'Getter' function for member m_key_events_rev

RevSlotMap & get_key_groups_rev ()

'Getter' function for member m key groups rev

unsigned int lookup_keyevent_key (long seqnum)

'Getter' function for member m_key_events_rev[seqnum];

long lookup_keyevent_seq (unsigned int keycode)

'Getter' function for member m_key_events_rev[keycode];

unsigned int lookup_keygroup_key (long groupnum)

'Getter' function for member m_key_events_rev[groupnum];

long lookup_keygroup_group (unsigned int keycode)

'Getter' function for member m_key_events_rev[keycode];

· virtual std::string key name (unsigned int key) const

Obtains the name of the key.

virtual void set_all_key_events ()

Provides base class functionality.

virtual void set_all_key_groups ()

Provides base class functionality.

• void set_key_event (unsigned int keycode, long sequence slot)

At construction time, this function sets up one keycode and one event slot.

void set key group (unsigned int keycode, long group slot)

At construction time, this function sets up one keycode and one group slot.

Protected Types

typedef std::map< unsigned int, long > SlotMap

This typedef defines a map in which the key is the keycode, that is, the integer value of a keystroke, and the value is the pattern/sequence number or slot.

typedef std::map< long, unsigned int > RevSlotMap

This typedef is like SlotMap, but used for lookup in the other direction.

Protected Member Functions

unsigned int * at bpm up ()

The following are tricky ways to get at address of the key and group operation values so that we don't directly expose the members to manipulation.

unsigned int * at_bpm_dn ()

'Getter' function for member m_key_bpm_dn

unsigned int * at_replace ()

'Getter' function for member m_key_replace

unsigned int * at_queue ()

'Getter' function for member m_key_queue

unsigned int * at_keep_queue ()

'Getter' function for member m_key_keep_queue

unsigned int * at_snapshot_1 ()

'Getter' function for member m_key_snapshot_1

unsigned int * at_snapshot_2 ()

'Getter' function for member m_key_snapshot_2

unsigned int * at_screenset_up ()

'Getter' function for member m_key_screenset_up

unsigned int * at_screenset_dn ()

'Getter' function for member m_key_screenset_dn

unsigned int * at_set_playing_screenset ()

'Getter' function for member m key playing screenset

• unsigned int * at_group_on ()

'Getter' function for member m_key_group_on

unsigned int * at_group_off ()

'Getter' function for member m_key_group_off

unsigned int * at_group_learn ()

'Getter' function for member m_key_group_learn

Private Attributes

bool m key show ui sequence key

If set, shows the shortcut-keys on each filled pattern slot in the main window.

'Getter' function for member m_key_show_ui_sequence_number

bool m_key_show_ui_sequence_number

If set, shows the sequence number on each filled pattern and empty pattern slot in the main window.

SlotMap m_key_events

Holds the mapping of keys to the pattern slots.

SlotMap m_key_groups

Holds the mapping of keys to the mute groups.

RevSlotMap m_key_events_rev

Holds the reverse mapping of the pattern slots to the keys.

RevSlotMap m_key_groups_rev

Holds the reverse mapping of the mute groups to the keys.

· unsigned int m key bpm up

Provides key assignments for some key sequencer features.

unsigned int m_key_bpm_dn

BPM down, semicolon.

unsigned int m_key_replace

Replace, Ctrl-L.

• unsigned int m_key_queue

Queue, Ctrl-R.

• unsigned int m_key_keep_queue

Keep queue, backslash.

• unsigned int m_key_snapshot_1

Snapshot 1, Alt-L.

unsigned int m_key_snapshot_2

Snapshot 1, Alt-R.

• unsigned int m_key_screenset_up

Set up, Right-].

unsigned int m_key_screenset_dn

Set down, Left-[.

· unsigned int m key set playing screenset

Set set, Home key.

• unsigned int m_key_group_on

Group on, igrave key.

• unsigned int m_key_group_off

Group off, apostrophe!

• unsigned int m_key_group_learn

Group learn, Insert.

unsigned int m_key_start

Start play, Space key.

• unsigned int m_key_pause

Pause play, Period.

unsigned int m_key_pattern_edit

Show pattern editor.

• unsigned int m_key_event_edit

Show event editor.

unsigned int m_key_stop

Stop play, Escape.

Friends

- class options
- class perform
- · class optionsfile

12.26.1 Detailed Description

It provides a way a mapping keystrokes to sequencer actions and song settings.

12.26.2 Member Typedef Documentation

```
12.26.2.1 typedef std::map<unsigned int, long> seq64::keys_perform::SlotMap [protected]
```

 $\textbf{12.26.2.2} \quad \textbf{typedef std::map} < \textbf{long, unsigned int} > \textbf{seq64::keys_perform::RevSlotMap} \quad \texttt{[protected]}$

12.26.3 Constructor & Destructor Documentation

```
12.26.3.1 seq64::keys_perform::keys_perform()
```

```
12.26.3.2 seq64::keys_perform::~keys_perform() [virtual]
```

Finally, any active patterns/sequences are deleted.

12.26.4 Member Function Documentation

```
12.26.4.1 void seq64::keys_perform::set_keys ( const keys_perform_transfer & kpt )
```

This structure holds all of the key settings from the File / Options / Keyboard tab dialog.

Parameters

kpt

The structure that holds the values of the keys to be used for various purposes in controlling a performance live.

12.26.4.2 void seq64::keys_perform::get_keys (keys_perform_transfer & kpt)

Parameters

kpt

The structure that holds the values of the keys to be used for various purposes in controlling a performance live.

```
12.26.4.3 unsigned int seq64::keys_perform::bpm_up() const [inline]
```

12.26.4.4 void seq64::keys_perform::bpm_up (unsigned int x) [inline]

Parameters

x The key value to assign to the operation.

```
12.26.4.5 unsigned int seq64::keys_perform::bpm_dn( )const [inline]
```

12.26.4.6 void seq64::keys_perform::bpm_dn (unsigned int x) [inline]

Parameters

x The key value to assign to the operation.

```
12.26.4.7 unsigned int seq64::keys_perform::replace( ) const [inline]
```

12.26.4.8 void seq64::keys_perform::replace (unsigned int x) [inline]

Parameters

x The key value to assign to the operation.

```
12.26.4.9 unsigned int seq64::keys_perform::queue( ) const [inline]
```

12.26.4.10 void seq64::keys_perform::queue (unsigned int x) [inline]

Parameters

x The key value to assign to the operation.

```
12.26.4.11 unsigned int seq64::keys_perform::keep_queue( )const [inline]
12.26.4.12 void seq64::keys_perform::keep_queue ( unsigned int x ) [inline]
Parameters
     The key value to assign to the operation.
12.26.4.13 unsigned int seq64::keys_perform::snapshot_1( ) const [inline]
12.26.4.14 void seq64::keys_perform::snapshot_1 ( unsigned int x ) [inline]
Parameters
     The key value to assign to the operation.
12.26.4.15 unsigned int seq64::keys_perform::snapshot_2( ) const [inline]
12.26.4.16 void seq64::keys_perform::snapshot_2 ( unsigned int x ) [inline]
Parameters
     The key value to assign to the operation.
12.26.4.17 unsigned int seq64::keys_perform::screenset_up()const [inline]
12.26.4.18 void seq64::keys_perform::screenset_up ( unsigned int x ) [inline]
Parameters
     The key value to assign to the operation.
12.26.4.19 unsigned int seq64::keys_perform::screenset_dn( ) const [inline]
12.26.4.20 void seq64::keys_perform::screenset_dn ( unsigned int x ) [inline]
Parameters
     The key value to assign to the operation.
12.26.4.21 unsigned int seq64::keys_perform::set_playing_screenset( ) const [inline]
12.26.4.22 void seq64::keys_perform::set_playing_screenset(unsigned int x) [inline]
```

```
Parameters
```

```
The key value to assign to the operation.
12.26.4.23 unsigned int seq64::keys_perform::group_on() const [inline]
12.26.4.24 void seq64::keys_perform::group_on(unsigned int x) [inline]
Parameters
     The key value to assign to the operation.
12.26.4.25 unsigned int seq64::keys_perform::group_off() const [inline]
12.26.4.26 void seq64::keys_perform::group_off(unsigned int x) [inline]
Parameters
     The key value to assign to the operation.
12.26.4.27 unsigned int seq64::keys_perform::group_learn( ) const [inline]
12.26.4.28 void seq64::keys_perform::group_learn ( unsigned int x ) [inline]
Parameters
     The key value to assign to the operation.
12.26.4.29
          unsigned int seq64::keys_perform::start( ) const [inline]
12.26.4.30 void seq64::keys_perform::start ( unsigned int x ) [inline]
Parameters
     The key value to assign to the operation.
12.26.4.31 unsigned int seq64::keys_perform::pause( ) const [inline]
12.26.4.32 void seq64::keys_perform::pause ( unsigned int x ) [inline]
```

Generated by Doxygen

The key value to assign to the operation.

Parameters

```
12.26.4.33 unsigned int seq64::keys_perform::pattern_edit() const [inline]
12.26.4.34 void seq64::keys_perform::pattern_edit ( unsigned int x ) [inline]
Parameters
     The key value to assign to the operation.
12.26.4.35 unsigned int seq64::keys_perform::event_edit( ) const [inline]
12.26.4.36 void seq64::keys_perform::event_edit( unsigned int x ) [inline]
Parameters
     The key value to assign to the operation.
12.26.4.37 unsigned int seq64::keys_perform::stop ( ) const [inline]
12.26.4.38 void seq64::keys_perform::stop ( unsigned int x ) [inline]
Parameters
     The key value to assign to the operation.
12.26.4.39 bool seq64::keys_perform::show_ui_sequence_key( ) const [inline]
Used in mainwid, options, optionsfile, userfile, and perform.
12.26.4.40 void seq64::keys_perform::show_ui_sequence_key( bool flag ) [inline]
Parameters
  flag
        The flag for showing the sequence key characters in each pattern slot.
12.26.4.41 bool seg64::keys_perform::show_ui_sequence_number() const [inline]
Used in mainwid, options, optionsfile, userfile, and perform.
12.26.4.42 void seq64::keys_perform::show_ui_sequence_number(bool flag) [inline]
Parameters
  flag
        The flag for showing the sequence number in each pattern slot.
```

12.26.4.43	SlotMap& seq64::keys_perform::get_key_events() [inline]
12.26.4.44	SlotMap& seq64::keys_perform::get_key_groups() [inline]
12.26.4.45	RevSlotMap& seq64::keys_perform::get_key_events_rev() [inline]
12.26.4.46	RevSlotMap& seq64::keys_perform::get_key_groups_rev() [inline]

12.26.4.47 unsigned int seq64::keys_perform::lookup_keyevent_key(long seqnum) [inline]

Parameters

seqnum	Provides the sequence number to look up in the reverse key map for patterns/sequences. If the
	count for this value is 0, then a question mark character is returned. Not checked for maximum!

12.26.4.48 long seq64::keys_perform::lookup_keyevent_seq (unsigned int keycode) [inline]

Parameters

keycode	Provides the keycode to look up in the (forward) key map for patterns/sequences. If the count for
	this value is 0, then a 0 is returned.

12.26.4.49 unsigned int seq64::keys_perform::lookup_keygroup_key(long groupnum) [inline]

Parameters

groupnum	Provides the group number to look up in the reverse key map for groups. If the count for this value
	is 0, then a question mark character is returned.

12.26.4.50 long seq64::keys_perform::lookup_keygroup_group (unsigned int keycode) [inline]

Parameters

keycode	Provides the sequence number to look up in the reverse key map for groups. If the count for this
	value is 0, then a 0 is returned.

12.26.4.51 std::string seq64::keys_perform::key_name(unsigned int key) const [virtual]

In gtkmm, this is done via the gdk_keyval_name() function. Here, in the base class, we just provide an easy-to-create string.

Parameters

kev	Provides the numeric value of the keystroke.

Returns

Returns the name of the key, in the format "Key 0xkkkk".

Reimplemented in seq64::keys_perform_gtk2.

```
12.26.4.52 virtual void seq64::keys_perform::set_all_key_events() [inline], [virtual]
```

Must be called by the derived-class's override of this function.

Reimplemented in seq64::keys_perform_gtk2.

```
12.26.4.53 virtual void seq64::keys_perform::set_all_key_groups() [inline], [virtual]
```

Must be called by the derived-class's override of this function.

Reimplemented in seq64::keys_perform_gtk2.

12.26.4.54 void seq64::keys_perform::set_key_event (unsigned int keycode, long sequence_slot)

It is called 32 times, corresponding the pattern/sequence slots in the Patterns window.

Parameters

keycode	The key to be assigned.
sequence_slot	The perform event slot into which the keycode will be assigned.

12.26.4.55 void seq64::keys_perform::set_key_group (unsigned int keycode, long group_slot)

It is called 32 times, corresponding the pattern/sequence slots in the Patterns window.

Parameters

keycode	The key to be assigned.
group_slot	The perform group slot into which the keycode will be assigned.

```
12.26.4.56 unsigned int* seq64::keys_perform::at_bpm_up() [inline], [protected]
```

They are used in the options module, and, for brevity, are accessed using the PREFKEY_ADDR() macro. 'Getter' function for member m key bpm up

Address getter for the bpm_up operation.

```
12.26.4.57 unsigned int* seq64::keys_perform::at_bpm_dn( ) [inline], [protected]
```

Address getter for the bpm_dn operation.

```
12.26.4.58 unsigned int* seq64::keys_perform::at_replace( ) [inline], [protected]
Address getter for the replace operation.
12.26.4.59 unsigned int* seq64::keys_perform::at_queue( ) [inline], [protected]
Address getter for the queue operation.
12.26.4.60 unsigned int* seq64::keys_perform::at_keep_queue( ) [inline], [protected]
Address getter for the keep_queue operation.
12.26.4.61 unsigned int* seq64::keys_perform::at_snapshot_1( ) [inline], [protected]
Address getter for the snapshot_1 operation.
12.26.4.62 unsigned int* seq64::keys_perform::at_snapshot_2( ) [inline], [protected]
Address getter for the snapshot_2 operation.
12.26.4.63 unsigned int* seq64::keys_perform::at_screenset_up() [inline], [protected]
Address getter for the screenset_up operation.
12.26.4.64 unsigned int* seq64::keys_perform::at_screenset_dn( ) [inline], [protected]
Address getter for the screenset_dn operation.
12.26.4.65 unsigned int* seq64::keys_perform::at_set_playing_screenset( ) [inline], [protected]
Address getter for the set_playing_screenset operation.
12.26.4.66 unsigned int* seq64::keys_perform::at_group_on() [inline], [protected]
Address getter for the group_on operation.
12.26.4.67 unsigned int* seq64::keys_perform::at_group_off( ) [inline], [protected]
Address getter for the group_off operation.
```

disabled in legacy mode.

```
12.26.4.68 unsigned int* seq64::keys_perform::at_group_learn() [inline], [protected]
Address getter for the group learn operation.
12.26.4.69 unsigned int* seq64::keys_perform::at_start( ) [inline], [protected]
Address getter for the start operation.
12.26.4.70 unsigned int* seq64::keys_perform::at_pause( ) [inline], [protected]
Address getter for the pause operation.
12.26.4.71 unsigned int* seq64::keys_perform::at_pattern_edit() [inline], [protected]
Address getter for the pattern edit operation.
12.26.4.72 unsigned int* seq64::keys_perform::at_event_edit( ) [inline], [protected]
Address getter for the event edit operation.
12.26.4.73 unsigned int* seq64::keys_perform::at_stop() [inline], [protected]
Address getter for the stop operation.
12.26.4.74 bool* seq64::keys_perform::at_show_ui_sequence_key( ) [inline], [protected]
Address getter for the show_ui_sequence_key value.
12.26.4.75 bool* seq64::keys_perform::at_show_ui_sequence_number() [inline], [protected]
Address getter for the show_ui_sequence_number value.
12.26.5 Friends And Related Function Documentation
12.26.5.1 friend class options [friend]
12.26.5.2 friend class perform [friend]
12.26.5.3 friend class optionsfile [friend]
12.26.6 Field Documentation
12.26.6.1 bool seq64::keys_perform::m_key_show_ui_sequence_key [private]
12.26.6.2 bool seq64::keys_perform::m_key_show_ui_sequence_number [private]
Also shows the sequence number as part of the sequence name in the performance window (song editor). Always
```

Generated by Doxygen

```
12.26.6.3 SlotMap seq64::keys_perform::m_key_events [private]
```

Do not access directly, use the set/lookup functions declared below.

```
12.26.6.4 SlotMap seq64::keys_perform::m_key_groups [private]
```

Do not access directly, use the set/lookup functions declared below.

```
12.26.6.5 RevSlotMap seq64::keys_perform::m_key_events_rev [private]
```

Do not access directly, use the set/lookup functions declared below.

```
12.26.6.6 RevSlotMap seq64::keys_perform::m_key_groups_rev [private]
```

Do not access directly, use the set/lookup functions declared below.

```
12.26.6.7 unsigned int seq64::keys_perform::m_key_bpm_up [private]
```

Used in mainwnd, options, optionsfile, perfedit, seqroll, userfile, and perform.

We could instead use the keys_perform_transfer structure instead of all these individual members.BPM up, apostrophe!!!

```
12.26.6.8 unsigned int seq64::keys_perform::m_key_bpm_dn [private]

12.26.6.9 unsigned int seq64::keys_perform::m_key_replace [private]

12.26.6.10 unsigned int seq64::keys_perform::m_key_queue [private]

12.26.6.11 unsigned int seq64::keys_perform::m_key_keep_queue [private]

12.26.6.12 unsigned int seq64::keys_perform::m_key_snapshot_1 [private]

12.26.6.13 unsigned int seq64::keys_perform::m_key_snapshot_2 [private]

12.26.6.14 unsigned int seq64::keys_perform::m_key_screenset_up [private]

12.26.6.15 unsigned int seq64::keys_perform::m_key_screenset_dn [private]

12.26.6.16 unsigned int seq64::keys_perform::m_key_screenset_ [private]


12.26.6.17 unsigned int seq64::keys_perform::m_key_screenset_ [private]
```



12.27 seq64::keys_perform_gtk2 Class Reference

This class supports the performance mode.

Inheritance diagram for seq64::keys_perform_gtk2:



Public Member Functions

keys_perform_gtk2 ()

This construction initializes a vast number of member variables, some of them public!

virtual ~keys_perform_gtk2 ()

A rote virtual destructor.

• virtual std::string key_name (unsigned int key) const

- virtual void set_all_key_events ()
 - Sets up the keys for arming/unmuting events in the Gtk-2 environment.
- virtual void set all key groups ()

Sets up the keys for group events in the Gtk-2 environment.

Additional Inherited Members

12.27.1 Detailed Description

It has way too many data members, many of the public. Might be ripe for refactoring.

12.27.2 Constructor & Destructor Documentation

```
12.27.2.1 seq64::keys_perform_gtk2::keys_perform_gtk2 ( )
```

12.27.2.2 seq64::keys_perform_gtk2::~keys_perform_gtk2() [virtual]

No action.

12.27.3 Member Function Documentation

12.27.3.1 virtual std::string seq64::keys_perform_gtk2::key_name(unsigned int key) const [inline], [virtual]

Reimplemented from seq64::keys_perform.

```
12.27.3.2 void seq64::keys_perform_gtk2::set_all_key_events( ) [virtual]
```

The base-class function call makes sure the the related lists are cleared before rebuilding them here.

Reimplemented from seq64::keys_perform.

```
12.27.3.3 void seq64::keys_perform_gtk2::set_all_key_groups() [virtual]
```

The base-class function call makes sure the the related lists are cleared before rebuilding them here.

Reimplemented from seq64::keys_perform.

12.28 seq64::keys_perform_transfer Struct Reference

Provides a data-transfer structure to make it easier to fill in a keys_perform object's members using sscanf().

Data Fields

- unsigned int kpt_bpm_up
- unsigned int kpt_bpm_dn
- · unsigned int kpt_screenset_up
- unsigned int kpt_screenset_dn
- unsigned int kpt_set_playing_screenset
- unsigned int kpt_group_on
- · unsigned int kpt_group_off
- unsigned int kpt_group_learn
- · unsigned int kpt replace
- unsigned int kpt_queue
- unsigned int kpt_keep_queue
- unsigned int kpt_snapshot_1
- unsigned int kpt_snapshot_2
- unsigned int kpt start
- unsigned int kpt_stop
- bool kpt_show_ui_sequence_key
- bool kpt_show_ui_sequence_number
- unsigned int kpt_pattern_edit
- unsigned int kpt_event_edit
- unsigned int kpt_pause

12.28.1 Field Documentation

12.28.1.1 unsigned int seq64::keys_perform_transfer::kpt_bpm_up

12.28.1.2 unsigned int seq64::keys_perform_transfer::kpt_bpm_dn

12.28.1.3 unsigned int seq64::keys_perform_transfer::kpt_screenset_up

12.28.1.4 unsigned int seq64::keys_perform_transfer::kpt_screenset_dn

12.28.1.5 unsigned int seq64::keys_perform_transfer::kpt_set_playing_screenset

12.28.1.6 unsigned int seq64::keys_perform_transfer::kpt_group_on

12.28.1.7 unsigned int seq64::keys_perform_transfer::kpt_group_off

12.28.1.8 unsigned int seq64::keys_perform_transfer::kpt_group_learn

12.28.1.9 unsigned int seq64::keys_perform_transfer::kpt_replace

12.28.1.10 unsigned int seq64::keys_perform_transfer::kpt_queue

12.28.1.11 unsigned int seq64::keys_perform_transfer::kpt_keep_queue

12.28.1.13 unsigned int seq64::keys_perform_transfer::kpt_snapshot_2

12.28.1.14 unsigned int seq64::keys_perform_transfer::kpt_start

12.28.1.15 unsigned int seq64::keys_perform_transfer::kpt_stop

12.28.1.16 bool seq64::keys_perform_transfer::kpt_show_ui_sequence_key

12.28.1.17 bool seq64::keys_perform_transfer::kpt_show_ui_sequence_number

12.28.1.18 unsigned int seq64::keys_perform_transfer::kpt_pattern_edit

12.28.1.19 unsigned int seq64::keys_perform_transfer::kpt_event_edit

12.28.1.20 unsigned int seq64::keys_perform_transfer::kpt_pause

12.29 seq64::keystroke Class Reference

Encapsulates any practical keystroke.

Public Member Functions

· keystroke ()

The default constructor for class keystroke.

The principal constructor.

keystroke (const keystroke &rhs)

Provides the rote copy constructor.

keystroke & operator= (const keystroke &rhs)

Provides the rote principal assignment operator.

• bool is_press () const

'Getter' function for member m_is_press

• bool is_letter (unsigned int ch=SEQ64_KEYSTROKE_BAD_VALUE) const

'Getter' function for member m_key to test letters, handles ASCII only.

· bool is (unsigned int ch) const

Tests the key value to see if it matches the given character exactly (no case-insensitivity).

• bool is_delete () const

'Getter' function for member m_key to test for a delete-causing key.

• unsigned int key () const

'Getter' function for member m key

• void shift lock ()

If a lower-case letter, a number, or another character on the "main" part of the keyboard, shift the m_key value to upper-case or the character shifted on a standard American keyboard.

• seq_modifier_t modifier () const

'Getter' function for member m_modifier

bool mod_control () const

'Getter' function for member m_modifier tested for Ctrl key.

bool mod_control_shift () const

'Getter' function for member m modifier tested for Ctrl and Shift key.

• bool mod_super () const

'Getter' function for member m_modifier tested for Mod4/Super/Windows key.

Private Attributes

• bool m_is_press

Determines if the key was a press or a release.

• unsigned int m_key

The key that was pressed or released.

• seq_modifier_t m_modifier

The optional modifier value.

12.29.1 Detailed Description

Useful in passing more generic events to non-GUI classes.

12.29.2 Constructor & Destructor Documentation

```
12.29.2.1 seq64::keystroke::keystroke ( )
```

12.29.2.2 seq64::keystroke::keystroke (unsigned int *key*, bool *press* = SEQ64_KEYSTROKE_PRESS, int *modkey* = int (SEQ64_NO_MASK))

Parameters

key	The keystroke number of the key that was pressed or released.
press	If true, the keystroke action was a press, otherwise it was a release.
modkey	The modifier key combination that was pressed, if any, in the form of a bit-mask, as defined in the gdk_basic_keys module. Common mask values are SEQ64_SHIFT_MASK, SEQ64_CONTROL_MASK, SEQ64_MOD1_MASK, and SEQ64_MOD4_MASK. If no modifier, this value is SEQ64_NO_MASK.

12.29.2.3 seq64::keystroke::keystroke (const keystroke & rhs)

Parameters

	The object to be copied.
rns	I he object to be copied
1110	The object to be depice.

12.29.3 Member Function Documentation

12.29.3.1 keystroke & seq64::keystroke::operator= (const keystroke & rhs)

Parameters

rhs	The object to be assigned.

Returns

Returns the reference to the current object, for use in assignment chains.

```
12.29.3.2 bool seq64::keystroke::is_press() const [inline]12.29.3.3 bool seq64::keystroke::is_letter( unsigned int ch = SEQ64_KEYSTROKE_BAD_VALUE ) const
```

Parameters

```
ch An optional character to test as an ASCII letter.
```

Returns

If a character is not provided, true is returned if it is an upper or lower-case letter. Otherwise, true is returned if the m_key value matches the character case-insensitively.

Tricky Code

```
12.29.3.4 bool seq64::keystroke::is ( unsigned int ch ) const [inline]
```

Parameters

```
ch The character to be tested.
```

Returns

Returns true if m_key == ch.

```
12.29.3.5 bool seq64::keystroke::is_delete( ) const [inline]
12.29.3.6 unsigned int seq64::keystroke::key( ) const [inline]
12.29.3.7 void seq64::keystroke::shift_lock( )
```

Currently also assumes the ASCII character set.

There's an oddity here: the shift of '2' is the '@' character, but seq24 seems to have treated it like the "" character. Some others were treated the same:

```
Key: 1 2 3 4 5 6 7 8 9 0
Shift: ! @ # $ % ^ & * ( )
Seq24: ! " # $ % & ' ( ) space
```

This function is meant to avoid using the Caps-Lock when picking a group-learn character in the group-learn mode.

```
12.29.3.8 seq_modifier_t seq64::keystroke::modifier() const [inline]

12.29.3.9 bool seq64::keystroke::mod_control() const [inline]

12.29.3.10 bool seq64::keystroke::mod_control_shift() const [inline]

12.29.3.11 bool seq64::keystroke::mod_super() const [inline]

12.29.4 Field Documentation

12.29.4.1 bool seq64::keystroke::m_is_press [private]
```

See the SEQ64_KEYSTROKE_PRESS and SEQ64_KEYSTROKE_RELEASE readability macros.

```
12.29.4.2 unsigned int seq64::keystroke::m_key [private]
```

Generally, the extended ASCII range (0 to 255) is supported. However, Gtk-2.x/3.x will generally support the full gamut of characters defined in the gdk_basic_keys.h module. We define minimum and maximum range macros for keystrokes that are a bit generous.

```
12.29.4.3 seq_modifier_t seq64::keystroke::m_modifier [private]
```

Note that SEQ64_NO_MASK is our word for 0, meaning "no modifier".

12.30 seq64::lash Class Reference

This class supports LASH operations, if compiled with LASH support (i.e.

Public Member Functions

• lash (perform &p, int argc, char **argv)

This constructor calls lash_extract(), using the command-line arguments, if SEQ64_LASH_SUPPORT is enabled.

· void set alsa client id (int id)

Make ourselves a LASH ALSA client.

• void start ()

Process any LASH events every 250 msec, which is an arbitrarily chosen interval.

bool process_events ()

Process LASH events.

Private Member Functions

• bool init ()

Initializes LASH support, if enabled.

void handle_event (lash_event_t *conf)

Handle a LASH event.

void handle_config (lash_config_t *conf)

Handle a LASH configuration item.

Private Attributes

• perform & m_perform

A hook into the single perform object in the application.

lash_client_t * m_client

Holds the client "handle" returned by the lash_init() function.

lash_args_t * m_lash_args

Holds the command-line arguments used by the lash_init() function.

• bool m_is_lash_supported

Indicates if LASH support has been compiled into the library.

12.30.1 Detailed Description

SEQ64_LASH_SUPPORT is defined). All of the ifdef skeleton work is done in this class in such a way that any other part of the code can use this class whether or not lash support is actually built in; the functions will just do nothing.

12.30.2 Constructor & Destructor Documentation

```
12.30.2.1 seq64::lash::lash ( perform & p, int argc, char ** argv )
```

We fixed the crazy usage of argc and argv here and in the client code in the seq24 module.

Parameters

р	The perform object that needs to implement LASH support.
argc	The number of command-line arguments.
argv	The command-line arguments.

12.30.3 Member Function Documentation

```
12.30.3.1 void seq64::lash::set_alsa_client_id ( int id )
```

/param id The ALSA client ID to be set.

```
12.30.3.2 void seq64::lash::start ( )
```

12.30.3.3 bool seq64::lash::process_events ()

Returns

Always returns true.

```
12.30.3.4 bool seq64::lash::init() [private]
```

Returns

Returns true if the LASH subsystem was able to be initialized, and a LASH client representative (m_client) was allocated.

12.30.3.5 void seq64::lash::handle_event(lash_event_t * ev) [private]

Parameters

ev Provides the event to be handled.

12.30.3.6 void seq64::lash::handle_config(lash_config_t * conf) [private]

Currently incomplete.

Parameters

conf Provides the configuration item to handle.

12.30.4 Field Documentation

```
12.30.4.1 perform& seq64::lash::m_perform [private]
```

12.30.4.2 lash_client_t* seq64::lash::m_client [private]

12.30.4.3 lash_args_t* seq64::lash::m_lash_args [private]


12.30.4.4 bool seq64::lash::m_is_lash_supported [private]

Is set to true if SEQ64_LASH_SUPPORT is defined. This variable is not used, but we will keep it around for the possibility of testing LASH support at run time.

12.31 seq64::Ifownd Class Reference

One LFO window class.

Inheritance diagram for seq64::lfownd:



Public Member Functions

- Ifownd (perform &p, sequence &seq, seqdata &sdata)
- virtual ∼lfownd ()
- void toggle_visible ()

Private Member Functions

- void scale_lfo_change ()
- bool on_focus_out_event (GdkEventFocus *p0)

Private Attributes

• sequence & m_seq

The sequence associated with this window.

• seqdata & m_seqdata

The seqdata associated with this window.

- Gtk::HBox * m_hbox
- Gtk::VScale * m scale value
- Gtk::VScale * m_scale_range
- Gtk::VScale * m_scale_speed
- Gtk::VScale * m scale phase
- Gtk::VScale * m_scale_wave
- · double m value
- double m_range
- double m_speed
- · double m phase
- wave_type_t m_wave

Additional Inherited Members

12.31.1 Detailed Description

Personally, it seems a bit of a odd duck to be included in Sequencer64, so we're thinking of a better way to manage the data managed by this window.

12.31.2 Constructor & Destructor Documentation

```
12.31.2.1 seq64::Ifownd::Ifownd ( perform & p, sequence & seq, seqdata & sdata )
```

```
12.31.2.2 seq64::Ifownd::\sim Ifownd() [virtual]
```

12.31.3 Member Function Documentation

```
12.31.3.1 void seq64::Ifownd::toggle_visible( )
```

12.31.3.2 void seq64::Ifownd::scale_lfo_change() [private]

12.31.3.3 bool seq64::Ifownd::on_focus_out_event(GdkEventFocus * p0) [private]


12.31.4 Field Documentation

```
12.31.4.1 sequence& seq64::lfownd::m_seq [private]
12.31.4.2 seqdata& seq64::Ifownd::m_seqdata [private]
12.31.4.3 Gtk::HBox* seq64::lfownd::m_hbox [private]
12.31.4.4 Gtk::VScale* seq64::Ifownd::m_scale_value [private]
12.31.4.5 Gtk::VScale* seq64::lfownd::m_scale_range [private]
12.31.4.6 Gtk::VScale* seq64::lfownd::m_scale_speed [private]
12.31.4.7 Gtk::VScale* seq64::lfownd::m_scale_phase [private]
12.31.4.8 Gtk::VScale* seq64::lfownd::m_scale_wave [private]
12.31.4.9 double seq64::lfownd::m_value [private]
12.31.4.10 double seq64::Ifownd::m_range [private]
12.31.4.11 double seq64::Ifownd::m_speed [private]
12.31.4.12 double seq64::lfownd::m_phase [private]
12.31.4.13 wave_type_t seq64::lfownd::m_wave [private]
```

12.32 seq64::maintime Class Reference

This class provides the drawing of the progress bar at the top of the main window, along with two "pills" that move in time with the beat and measure.

Inheritance diagram for seq64::maintime:



Public Member Functions

- maintime (perform &p, int ppqn=SEQ64_USE_DEFAULT_PPQN)
 - This constructor sets up the colors black, white, and grey, and then allocates them.
- virtual ∼maintime ()

Let's provide a do-nothing virtual destructor.

Private Member Functions

- maintime (const maintime &)
- maintime & operator= (const maintime &)
- int idle progress (midipulse ticks)

This function clears the window, sets the foreground to black, draws the "time" window's rectangle, and then draws a rectangle for noting the progress of the beat, and the progress for a bar.

• void on_realize ()

Handles realization of the window.

bool on expose event (GdkEventExpose *ev)

This function merely idles.

Private Attributes

· const int m beat width

Provides the divisor for ticks to produce a beat value.

· const int m bar width

Provides the divisor for ticks to produce a bar value.

· const int m pill width

Provides the width of the pills, little black squares that show the progress of a beat and a bar (measure).

• const int m_box_width

The width/length of the rectangle to be drawn inside the maintime window.

· const int m box height

The height of the rectangle to be drawn inside the maintime window.

• const int m_flash_width

The width/length of the flashing rectangle to be drawn inside the maintime window.

const int m_flash_height

The height of the flashing rectangle to be drawn inside the maintime window.

· const int m flash x

The x value at which a flash should occur.

• const int m_box_less_pill

The width/length of the maintime window minus the width of the pill.

· midipulse m tick

Saves the tick value for on_expose_event().

• int m_ppqn

Provides the active PPQN value.

Friends

· class mainwnd

Additional Inherited Members

12.32.1 Detailed Description

We added a lot of members to hold the results of calculations that involve what are essentially constant. This saves CPU time, and maybe a little memory for the code to make those calculations more than once.

12.32.2 Constructor & Destructor Documentation

```
12.32.2.1 seq64::maintime::maintime ( const maintime & ) [private]
```

```
12.32.2.2 seq64::maintime::maintime ( perform & p, int ppqn = SEQ64_USE_DEFAULT_PPQN )
```

In the constructor you can only allocate colors; get_window() would return 0 because the windows has not yet been realized.

```
12.32.2.3 virtual seq64::maintime::~maintime() [inline], [virtual]
```

12.32.3 Member Function Documentation

```
12.32.3.1 maintime& seq64::maintime::operator=( const maintime & ) [private]
```

```
12.32.3.2 int seq64::maintime::idle_progress ( midipulse ticks ) [private]
```

Idle hands do the devil's work. We should eventually support some generic coloring for "dark themes". The default coloring is better for "light themes".

Parameters

ticks Provides the main tick setting. This setting is provided by mainwnd(), in its timer callback.

Returns

Always returns 1 (it used to return "true"!).

```
12.32.3.3 void seq64::maintime::on_realize( ) [private]
```

It performs the base class's on_realize() function. It then allocates some additional resources: a window, a GC (?), and it clears the window. Then it sets the default size of the window, specified by GUI constructor parameters.

```
12.32.3.4 bool seq64::maintime::on_expose_event ( GdkEventExpose * a_e ) [private]
```

We don't need the m_tick member, the function works as well if 0 is passed in. We've removed m_tick permanently.

Actually, it might be useful after all, to avoid flickering under JACK transport. Let's put it back for now. (It doesn't help, but we will leave it in, the overhead is small.)

12.32.4 Friends And Related Function Documentation

```
12.32.4.1 friend class mainwnd [friend]
```

12.32.5 Field Documentation

12.32.5.1 const int seq64::maintime::m_beat_width [private]

Currently, this value is hardwired to 4, but will eventually be wired up as usr().midi_beat_width().

```
12.32.5.2 const int seq64::maintime::m_bar_width [private]
```

Currently, this value is hardwired to 16, but will eventually be wired up as usr().midi_beat_width() * usr().midi_\circ
beats_per_bar().

```
12.32.5.3 const int seq64::maintime::m_pill_width [private]
```

```
12.32.5.4 const int seq64::maintime::m_box_width [private]
```

This item absolutely depends on the main window being non-resizable.

```
12.32.5.5 const int seq64::maintime::m_box_height [private]
```

This item absolutely depends on the main window being non-resizable.

```
12.32.5.6 const int seq64::maintime::m_flash_width [private]
```

Just a bit smaller than m_box_width.

12.32.5.7 const int seq64::maintime::m_flash_height [private]

Just a bit smaller than m_box_width.

12.32.5.8 const int seq64::maintime::m_flash_x [private]

12.32.5.9 const int seq64::maintime::m_box_less_pill [private]

12.32.5.10 midipulse seq64::maintime::m_tick [private]

It might actually be useful after all. And the overhead is tiny.


12.32.5.11 int seq64::maintime::m_ppqn [private]

While this is effectively a constant for the duration of a tune, it might change as different tunes are loaded.

12.33 seq64::mainwid Class Reference

This class implements the piano roll area of the application.

Inheritance diagram for seq64::mainwid:



Public Member Functions

mainwid (perform &p)

This constructor sets all of the members.

virtual ∼mainwid ()

A rote destructor.

void set screenset (int ss, bool setperf=false)

Set the current screen-set.

Private Member Functions

· void reset ()

This function redraws everything and queues up a redraw operation.

void update_sequences_on_window ()

Updates the image of multiple sequencer/pattern slots.

void draw_pixmap_on_window ()

This function queues the blit of pixmap to window.

· void fill background window ()

This function updates the background window, clearing it.

virtual void redraw (int seq)

This virtual function, overridden from the segmenu base class, draws the the given pattern/sequence again.

virtual void seg set and edit (int segnum)

Calculates the sequence number based on the screenset and then calls the base-class function to bring up the pattern/sequence editor.

virtual void seq_set_and_eventedit (int seqnum)

Calculates the sequence number based on the screenset and then calls the base-class function to bring up the event editor

void draw_marker_on_sequence (int seq, int tick)

Does the actual drawing of one pattern/sequence position marker, a vertical progress bar.

void update_markers (int ticks)

Draw the cursors (long vertical bars) on each sequence, so that they follow the playing progress of each sequence in the mainwid (Patterns Panel).

bool valid sequence (int seq)

Common-code helper function.

• void draw_sequence_on_pixmap (int seq)

This function draws a specific pattern/sequence on the pixmap located in the main window of the application, the Patterns Panel.

void draw_sequences_on_pixmap ()

This function fills the pixmap with sequences.

void draw_sequence_pixmap_on_window (int seq)

This function draws a sequence pixmap in the Patterns Panel.

int seq_from_xy (int x, int y)

Translates XY coordiinates in the Patterns Panel to a sequence number.

• int timeout ()

Provides a stock callback, because some kind of callback is needed.

void calculate_base_sizes (int seq, int &basex, int &basey)

Provides a way to calculate the base x and y size values for the pattern map.

void select_fg_bg_colors (int seqnum)

Picks the foreground and background colors based on the sequence in edit and the SEQ64_EDIT_SEQUENCE_← HIGHLIGHT macro.

· void on realize ()

For this GTK callback, on realization of window, initialize the shiz.

• bool on expose event (GdkEventExpose *ev)

Implements the GTK expose event callback.

• bool on_button_press_event (GdkEventButton *ev)

Handles a press of a mouse button in one of the sequence/pattern slots.

bool on_button_release_event (GdkEventButton *ev)

Handles a release of a mouse button.

bool on_motion_notify_event (GdkEventMotion *p0)

Handle the motion of the mouse if a mouse button is down and in another sequence and if the current sequence is not in edit mode.

bool on_focus_in_event (GdkEventFocus *)

Handles an on-focus event.

bool on_focus_out_event (GdkEventFocus *)

Handles an out-of-focus event.

Private Attributes

sequence m_moving_seq

Holds a partial copy of the sequence we are moving on the patterns panel.

• bool m_button_down

Indicates that the mouse button is still down.

bool m_moving

Indicates that we are still in the middle of a drag-and-drop operation.

int m_old_seq

Holds the sequence number of a sequence being drag-and-dropped.

• int m_screenset

Indicates the current screenset that is visible.

long m_last_tick_x [c_max_sequence]

Holds the last active tick for each sequence, used in erasing the progress bar.

int m_mainwnd_rows

These values are assigned to the values given by the constants of similar names in globals.h, and we will make them parameters or user-interface configuration items later.

• int m_mainwnd_cols

Number of columns, unused in settings.

• int m_seqarea_x

Roughly with width of the main window.

int m_seqarea_y

Roughly with height of the main window.

• int m_seqarea_seq_x

To be determined.

int m_seqarea_seq_y

To be determined.

· int m mainwid x

To be determined.

int m_mainwid_y

To be determined.

· int m mainwid border

Main-window border, unused setting.

int m_mainwid_spacing

Main-window spacing, unused setting.

· int m_text_size_x

Text width, varies with font in use.

int m_text_size_y

Text height, varies with font in use.

· int m_max_sets

The maximum number of sets, use all over.

· int m screenset slots

Provides a convenience variable for avoiding multiplications.

int m_screenset_offset

Provides a convenience variable for avoiding multiplications.

· int m progress height

Provides the height of the progress bar, to save calculations and for consistency between drawing and erasing the progress bar.

Friends

- · class mainwnd
- void update mainwid sequences ()

This global function in the seq64 namespace calls mainwid :: update_sequences_on_window(), if the global mainwid object exists.

Additional Inherited Members

12.33.1 Detailed Description

It inherits from gui_drawingarea_gtk2 to support the font, color, and other GUI functionality, and from seqmenu to support the right-click Edit/New/Cut right-click menu. The friend class and function are for updating the current sequence and for control via the mainward object.

12.33.2 Constructor & Destructor Documentation

```
12.33.2.1 seq64::mainwid::mainwid ( perform & p )
```

And it asks for a size of c_mainwid_x by c_mainwid_y. It adds GDK masks for button presses, releases, motion, key presses, and focus changes. Also logs a self-referential singleton pointer to use for the current-edit highlighting support.

Parameters

p Provides the reference to the all-important perform object.

```
12.33.2.2 seq64::mainwid::~mainwid() [virtual]
```

12.33.3 Member Function Documentation

12.33.3.1 void seq64::mainwid::set_screenset (int ss, bool setperf = false)

The clamping algorithm for the screeset is a bit weird: if less than 0, we set m_screenset to its maximum, and if greater than the maximum, we set it to its minimum. Not sure if this matters.

Note that m_screenset_slots = m_mainwnd_rows * m_mainwnd_cols.

We will likely replace this with perform::set_screenset(), which recapitulates the code above completely, whereas perform::set-offset() recapitulates only the line of code immediately above it. However, note that there is a back-and-forth between setting the screenset via perform (using MIDI control) versus the GUI in the mainward class. Probably useful to add a default boolean to prevent circular manipulation.

Parameters

ss	Provides the screen-set number to set.
setperf	If true, then also call perfrom::set_screenset().

```
12.33.3.2 void seq64::mainwid::reset( ) [inline], [private]
12.33.3.3 void seq64::mainwid::update_sequences_on_window( ) [inline], [private]
```

Used by the friend class mainwnd, but also useful for our new feature to fully highlight the current sequence. Calls reset() if SEQ64_EDIT_SEQUENCE_HIGHLIGHT is defined.

```
12.33.3.4 void seq64::mainwid::draw_pixmap_on_window( ) [inline],[private]
12.33.3.5 void seq64::mainwid::fill_background_window( ) [inline],[private]
12.33.3.6 void seq64::mainwid::redraw(int seqnum) [private],[virtual]
```

Parameters

seqnun	Provides the number of the sequence to draw	<i>1</i> .
--------	---	------------

Implements seq64::segmenu.

```
12.33.3.7 void seq64::mainwid::seq_set_and_edit(int seqnum) [private], [virtual]
```

Used with the '=' key selection, by default.

Reimplemented from seq64::seqmenu.

```
12.33.3.8 void seq64::mainwid::seq_set_and_eventedit(int seqnum) [private], [virtual]
```

Used with the '-' key selection, by default.

Reimplemented from seq64::segmenu.

```
12.33.3.9 void seq64::mainwid::draw_marker_on_sequence( int seqnum, int tick ) [private]
```

If the sequence has no events, this function doesn't bother even drawing a position marker.

Note that, when Sequencer64 first comes up, and perform::is_dirty_main() is called, no sequences exist yet. Also, currently the redraw() is hit when seq_edit() is called, but not when seq_event_edit() is called, which makes the latter not paint the in-edit highlight colors (if enabled). Why?

Parameters

seqnum	Provides the number of the sequence to draw.
tick	Provides the location to draw the marker. If pause support is compiled in (i.e. no –disable-pause in the configuration), then this parameter is ignored, and is replaced by the sequences' get_lask_tick() value. This causes correct stop/pause/play progress-bar behavior in each pattern slot.

12.33.3.10 void seq64::mainwid::update_markers (int tick) [private]

Parameters

tick Starting point for drawing the m	narkers.
---------------------------------------	----------

12.33.3.11 bool seq64::mainwid::valid_sequence(int seqnum) [private]

Parameters

	seqnum	Provides the number of the sequence to validate.
--	--------	--

Returns

Returns true if the sequence number is valid for the current m_screenset value.

12.33.3.12 void seq64::mainwid::draw_sequence_on_pixmap(int seqnum) [private]

The sequence is drawn only if it is in the current screen set (indicated by m_screenset). Also, we ignore the sequence if it does not exist.

Note

If only the main window is up, then the sequences just play (muted by default) – the progress bars move in each pattern. Gaps in the sequence in the Song (performance) Editor don't change the appearance of the patterns if only the main window is up. But, if the Song Editor window is up, and the song is started using the controls in the Song Editor, then the active patterns are black while playing, and white when gaps in the sequence are encountered. The muting status in the main window is ignored. The muting in the Song (performance) windows is in force. This setup holds for ALSA, but not for JACK transport.

Parameters

seqnum	Provides the number of the sequence slot that needs to be drawn. It is checked for validity before
	usage.

12.33.3.13 void seq64::mainwid::draw_sequences_on_pixmap() [private]

Please note that draw_sequence_on_pixmap() also draws the empty slots of inactive sequences, so we cannot take shortcuts here.

12.33.3.14 void seq64::mainwid::draw_sequence_pixmap_on_window(int seqnum) [private]

The sequence is drawn only if it is in the current screen set (indicated by m_screenset. This function is used when dragging a pattern from one pattern-slot to another pattern-slot.

We have to add 1 pixel to the y height in order to avoid leaving behind a line at the bottom of an empty pattern-slot.

Parameters

seqnum	Provides the number of the sequence to draw.
--------	--

12.33.3.15 int seq64::mainwid::seq_from_xy (int x, int y) [private]

Parameters

Χ	Provides the x coordinate.
У	Provides the y coordinate.

Returns

Returns -1 if the sequence number cannot be calculated.

12.33.3.16 int seq64::mainwid::timeout() [private]

Todo We should use this callback to display the current time in the playback.

Returns

Always returns true.

12.33.3.17 void seq64::mainwid::calculate_base_sizes (int seqnum, int & basex, int & basey) [private]

The values are returned as side-effects.

Parameters

		seqnum	Provides the number of the sequence to calculate.
ĺ	out	basex	A return parameter for the x coordinate of the base size.
ſ	out	basey	A return parameter for the y coordinate of the base size.

12.33.3.18 void seq64::mainwid::select_fg_bg_colors (int seqnum) [private]

12.33.3.19 void seq64::mainwid::on_realize() [private]

It allocates any additional resources that weren't initialized in the constructor.

This function used to call font::init(), and was the only place where the font::init() function was called. The init() function gets a color-map from the window. We need a more fool-proof was to do this!

12.33.3.20 bool seq64::mainwid::on_expose_event (GdkEventExpose * ev) [private]

Parameters

ev The expose event.

Returns

Always returns true.

12.33.3.21 bool seq64::mainwid::on_button_press_event (GdkEventButton * ev) [private]

If the press is a single left-click, and no Ctrl key is pressed, then this function grabs the focus, calculates the pattern/sequence over which the button press occurred, and sets the m_button_down flag if it is over a pattern. In the release event callback, this then causes the sequence arming/muting to be toggled.

If the press is a single Ctrl-left-click, this function brings up the New or Edit menu. The New menu is brought up if the grid slot is empty, and the Edit menu otherwise. Another way to bring up the same functionality is described in the next paragraph.

If the press is a double-click, it first acts just like two single-clicks (which might confuse the user at first, because it toggles the mute state twice). Then it brings up the Edit menu for the sequence. This new behavior is closer to what users have come to expect from a double-click. I miss the double-click when running seq24.

We also try to handle a Ctrl-double-click as a signal to do an event edit, instead of a sequence edit. The event editor provides a way to look at all events in detail, without having to select the type of event to see. However, this doesn't work, the event is treated like a ctrl-single-click. And we use the Alt key to enable window movement or resizing in our window manager, so that's out.

Parameters

ev Provides the parameters of the button event.

Returns

Always returns true.

12.33.3.22 bool seq64::mainwid::on_button_release_event(GdkEventButton * ev) [private]

This event is a lot more complex than a press. The left button toggles playback status. The right button brings up a popup menu. If the slot is empty, then a "New" popup is presented, otherwise an "Edit" and selection popup is presented.

Also now implements the new "toggle all other patterns" action, initiated via Shift-Left-Click.

Parameters

ev Provides the parameters of the button event.

Returns

Always returns true.

Tried disabling the setting of the current sequence; it completely disables drag-n-drop. But leaving it in removes the current-sequence highlighting, which otherwise is fine. So we do it only if moving a pattern (drag-and-drop).

```
12.33.3.23 bool seq64::mainwid::on_motion_notify_event( GdkEventMotion * ev ) [private]
```

This function moves the selected pattern to another pattern slot. The perform::delete_sequence() function sets the perform modification flag.

Parameters

ev Provides the parameters of the button event.

Returns

Always returns true.

```
12.33.3.24 bool seq64::mainwid::on_focus_in_event( GdkEventFocus * ) [private]
```

Just sets the Gtk::HAS_FOCUS flag.

Returns

Always returns false.

```
12.33.3.25 bool seq64::mainwid::on_focus_out_event ( GdkEventFocus * ) [private]
```

Just unsets the Gtk::HAS_FOCUS flag.

Returns

Always returns false.

12.33.4 Friends And Related Function Documentation

```
12.33.4.1 friend class mainwnd [friend]
```

```
12.33.4.2 void update_mainwid_sequences( ) [friend]
```

It is used by other objects that can modify the currently-edited sequence shown in the mainwid (main window).

```
12.33.5 Field Documentation
```

```
12.33.5.1 sequence seq64::mainwid::m_moving_seq [private]
```

The assignment is made by sequence::partial_copy(), which behaves like the legacy seq24 code.

```
12.33.5.2 bool seq64::mainwid::m_button_down [private]
```

Used in the drag-and-drop functionality.

```
12.33.5.3 bool seq64::mainwid::m_moving [private]
```

```
12.33.5.4 int seq64::mainwid::m_old_seq [private]
```

```
12.33.5.5 int seq64::mainwid::m_screenset [private]
```

12.33.5.6 long seq64::mainwid::m_last_tick_x[c_max_sequence] [private]

```
12.33.5.7 int seq64::mainwid::m_mainwnd_rows [private]
```

Some of them already have counterparts in the user_settings class. Number of rows, unused part of settings.

```
12.33.5.8 int seq64::mainwid::m_mainwnd_cols [private]
```

```
12.33.5.9 int seq64::mainwid::m_seqarea_x [private]
```

```
12.33.5.10 int seq64::mainwid::m_seqarea_y [private]
```

12.33.5.11 int seq64::mainwid::m_seqarea_seq_x [private]

12.33.5.12 int seq64::mainwid::m_seqarea_seq_y [private]

12.33.5.13 int seq64::mainwid::m_mainwid_x [private]

12.33.5.14 int seq64::mainwid::m_mainwid_y [private]

12.33.5.15 int seq64::mainwid::m_mainwid_border [private]

12.33.5.16 int seq64::mainwid::m_mainwid_spacing [private]

12.33.5.17 int seq64::mainwid::m_text_size_x [private]

12.33.5.18 int seq64::mainwid::m_text_size_y [private]


12.33.5.19 int seq64::mainwid::m_max_sets [private]

12.33.5.20 int seq64::mainwid::m_screenset_slots [private]

It is equal to m_mainwnd_rows * m_mainwnd_cols.



Inheritance diagram for seq64::mainwnd:



Public Member Functions

- mainwnd (perform &p, bool allowperf2=true, int ppqn=SEQ64_USE_DEFAULT_PPQN)
 - The constructor the main window of the application.
- virtual ∼mainwnd ()

This destructor must explicitly delete some allocated resources.

• void open_file (const std::string &filename)

Opens and parses (reads) a MIDI file.

• int ppqn () const

'Getter' function for member m_ppqn

void ppqn (int ppqn)

'Setter' function for member m_ppqn We can't set the PPQN value when the mainwnd is created, we have to do it later, using this function.

Private Member Functions

void adj_callback_ss ()

This function is the callback for adjusting the screen-set value.

void adj callback bpm ()

This function is the callback for adjusting the BPM value.

void edit_callback_notepad ()

A callback function for handling an edit to the screen-set notepad.

• bool timer callback ()

This function is the GTK timer callback, used to draw our current time and BPM on_events (the main window).

• void set_image (bool isrunning)

Changes the image used for the pause/play button.

void start playing ()

Starts playing of the song.

void pause playing ()

Pauses the playing of the song, leaving the progress bar where it stopped.

void stop_playing ()

Stops the playing of the song.

void toggle_playing ()

Reverses the state of playback.

void learn_toggle ()

Toggle the group-learn status.

void open_performance_edit ()

Opens the Performance Editor (Song Editor).

void open_performance_edit_2 ()

Opens the second Performance Editor (Song Editor).

void enregister_perfedits ()

This function brings together the two perfedit objects, so that they can tell each other when to queue up a draw operation.

void sequence_key (int seq)

Use the sequence key to toggle the playing of an active pattern in the current screen-set.

void update window title ()

Updates the title shown in the title bar of the window.

• void toLower (std::string &)

Converts a string to lower-case letters.

void file_new ()

A callback function for the File / New menu entry.

• void file_open ()

A callback function for the File / Open menu entry.

void file_save ()

A callback function for the File / Save menu entry.

void set_song_mute (perform::mute_op_t op)

Sets the song-mute mode.

· void file_import_dialog ()

Presents a file dialog to import a MIDI file.

· void options_dialog ()

Opens the File / Options dialog.

void about_dialog ()

Presents a Help / About dialog.

• int query_save_changes ()

Queries the user to save the changes made while the application was running.

void new_open_error_dialog ()

Tells the user to close all the edit windows first.

• void file_save_as (bool do_export=false)

A callback function for the File / Save As menu entry.

• void file_exit ()

A callback function for the File / Exit menu entry.

· void new file ()

Actually does the work of setting up for a new file.

• bool save_file ()

Saves the current state in a MIDI file.

• void choose file ()

Creates a file-chooser dialog.

• bool is_save ()

If the data is modified, then the user is queried, and the file is save if okayed.

bool install_signal_handlers ()

Installs the signal handlers and pipe code.

bool signal action (Glib::IOCondition condition)

Handles saving or exiting actions when signalled.

bool on_delete_event (GdkEventAny *ev)

This callback function handles a delete event from ...?

bool on_key_press_event (GdkEventKey *ev)

Handles a key press event.

bool on_key_release_event (GdkEventKey *ev)

Handles a key release event.

• virtual void on_grouplearnchange (bool state)

Notification handler for learn mode toggle.

Static Private Member Functions

static void handle_signal (int sig)

This function is the handler for system signals (SIGUSR1, SIGINT...) It writes a message to the pipe and leaves as soon as possible.

Private Attributes

• Gtk::Tooltips * m tooltips

A repository for tooltips.

Gtk::MenuBar * m_menubar

Theses objects support the menu and its sub-menus.

• Gtk::Menu * m menu file

The File menu entry.

 Gtk::Menu * m_menu_edit The (new) Edit menu entry. • Gtk::Menu * m menu view The View menu entry. • Gtk::Menu * m_menu_help The Help menu entry. • int m_ppqn Saves the PPQN value obtained from the MIDI file (or the default value, the global ppqn, if SEQ64_USE_DEFAUL↔ T_PPQN was specified in reading the MIDI file. mainwid * m main wid The biggest sub-components of mainwnd. · maintime * m main time Is this the bar at the top that shows moving squares, also known as "pills"? Why yes, it is. perfedit * m perf edit A pointer to the first song/performance editor. perfedit * m_perf_edit_2 A pointer to an optional second song/performance editor. options * m_options A pointer to the program options. Gdk::Cursor m_main_cursor Mouse cursor? Gtk::Image * m_image_play Provides a pointer to hold the images for the pause/play button. • Gtk::Button * m button learn This button is the learn button, otherwise known as the "L" button. Gtk::Button * m_button_stop Implements the red square stop button. Gtk::Button * m_button_play Implements the green triangle play button. • Gtk::Button * m_button_perfedit The button for bringing up the Song Editor (Performance Editor). Gtk::Adjustment * m_adjust_bpm The spin/adjustment controls for the BPM (beats-per-minute) value. • Gtk::SpinButton * m_spinbutton_bpm BPM spin-button object. Gtk::Adjustment * m adjust ss The spin/adjustment controls for the screenset value. Gtk::SpinButton * m spinbutton ss Screenset adjustment. Gtk::Adjustment * m_adjust_load_offset The spin/adjustment controls for the load offset value. Gtk::SpinButton * m_spinbutton_load_offset Spin button for import. Gtk::Entry * m_entry_notes This item provides user-interface access to the screenset notepad editor. bool m is running

Holds the current status of running, for use in display the play versus pause icon.

sigc::connection m timeout connect

Provides a timeout handler.

· bool m menu mode

Indicates if the menu bar is to be greyed out or not.

• bool m_call_seq_edit

Indicates that this object is in a mode where the usual mute/unmute keystroke will instead bring up the pattern slot for editing

· bool m call seq eventedit

Indicates that this object is in a mode where the usual mute/unmute keystroke will instead bring up the pattern slot for event-editing.

Static Private Attributes

static int m_sigpipe [2]

This small array holds the "handles" for the pipes need to intercept the system signals SIGINT and SIGUSR1, so that the application shuts down gracefully when aborted.

Additional Inherited Members

12.34.1 Constructor & Destructor Documentation

```
12.34.1.1 seq64::mainwnd::mainwnd(perform & p, bool allowperf2 = true, int ppqn = SEQ64_USE_DEFAULT_PPQN
)
```

This constructor is way too large; it would be nicer to provide a number of well-named initialization functions.

Parameters

р	Refers to the main performance object.
allowperf2 Indicates if a second perfedit window should be created. This is currently a run-time selectable in the "user" configuration file.	Indicates if a second perfedit window should be created. This is currently a run-time option, selectable in the "user" configuration file.
ppqn An optional PPQN value to use in the song.	

Todo Offload most of the work into an initialization function like options does; make the perform parameter a reference; valgrind flags m_tooltips as lost data, but if we try to manage it ourselves, many more leaks occur.

View menu items and their hot keys. It repeats the song editor edit command, just to help those whose muscle memory is already seq32-oriented.

View menu items and their hot keys.

Help menu items

Top panel items, including the logo (updated for the new version of this application) and the "timeline" progress bar.

```
12.34.1.2 seq64::mainwnd::~mainwnd() [virtual]
```

12.34.2 Member Function Documentation

```
12.34.2.1 void seq64::mainwnd::open_file ( const std::string & fn )
```

We leave the ppqn parameter set to the SEQ64_USE_DEFAULT for now, to preserve the legacy behavior of using the global ppqn, and scaling the running time against the PPQN read from the MIDI file. Later, we can provide a value like 0, that will certainly be changed by reading the MIDI file.

We don't need to specify the "oldformat" or "global sequence" parameters of the midifile constructor when reading the MIDI file, since reading handles both the old and new formats, dealing with new constructs only if they are present in the file.

Parameters

```
fn Provides the file-name for the MIDI file to be opened.
```

```
12.34.2.2 int seq64::mainwnd::ppqn( ) const [inline]
12.34.2.3 void seq64::mainwnd::ppqn(int ppqn) [inline]
m_ppqn = choose_ppqn(ppqn);
12.34.2.4 void seq64::mainwnd::handle_signal(int sig) [static], [private]
12.34.2.5 void seq64::mainwnd::adj_callback_ss() [private]
```

Its sets the screen-set value in the Performance/Song window, the Patterns, and something about setting the text based on a screen-set notepad from the Performance/Song window. We let the perform object keep track of modifications.

```
12.34.2.6 void seq64::mainwnd::adj_callback_bpm() [private]
```

Let the perform object keep track of modifications.

```
12.34.2.7 void seq64::mainwnd::edit_callback_notepad( ) [private]
```

Let the perform object keep track of modifications.

```
12.34.2.8 bool seq64::mainwnd::timer_callback( ) [private]
```

It also supports the ALSA pause functionality.

Note

When Sequencer64 first starts up, and no MIDI tune is loaded, the call to mainwid::update_markers() leads to trying to do some work on sequences that don't yet exist. Also, if a sequence is changed by the event editor, we get a crash; need to find out how sequence away with the changes.

```
12.34.2.9 void seq64::mainwnd::set_image ( bool isrunning ) [private]
```

Parameters

isrunning	If true, set the image to the "Pause" icon, since playback is running. Otherwise, set it to the "Play"	1
	button, since playback is not running.	

```
12.34.2.10 void seq64::mainwnd::start_playing() [private]
```

The rc_settings::song_start_mode() function is used (if JACK is running, though this will change soon) to determine if the playback mode is "live" (false) or "song" (true). An accessor to perform::start_playing(). This function is actually a callback for the pause/play button.

Note

This overrides the old behavior of playing live mode if the song is started from the main window. So let's go back to the way seq24 handles it. We could also make it dependent on the –legacy option, but that's too much trouble for now.

```
12.34.2.11 void seg64::mainwnd::pause_playing() [private]
```

Currently, it is just the same as stop_playing(), but we will get it to work.

```
12.34.2.12 void seq64::mainwnd::stop_playing() [private]
```

An accessor to perform's stop_playing() function. Also calls the mainwid::update_sequences_on_window() function. Not sure that we need this call, since the slots seem to update anyway. But we've noticed that, with this call in place, hitting the Stop button causes a subtle change in the appearance of the first non-empty pattern of the "allofarow.mid" file.

After the Stop button is pushed (in ALSA mode), then the Space key ("start") doesn't work properly. The song starts, then quickly stops. It doesn't matter if update_sequences_on_window() is called or not. This happens even in seq24! This bug has proven incredibly difficult to track down, still working on it.

```
12.34.2.13 void seq64::mainwnd::toggle_playing( ) [private]
```

Meant only to be called when the "Play" button is pressed, if the pause feature has been compiled into the application.

```
12.34.2.14 void seq64::mainwnd::learn_toggle() [inline], [private]
```

Simply forwards the call to perform::learn_toggle().

```
12.34.2.15 void seq64::mainwnd::open_performance_edit( ) [private]
```

We will let perform keep track of modifications, and not just set an is-modified flag just because we opened the song editor. We're going to centralize the modification flag in the perform object, and see if it can work.

```
12.34.2.16 void seq64::mainwnd::open_performance_edit_2( ) [private]
```

Experiment: open a second one and see what happens. It works, but one needs to tell the other to redraw if a change is made.

```
12.34.2.17 void seq64::mainwnd::enregister_perfedits( ) [private]
12.34.2.18 void seq64::mainwnd::sequence_key(int seq ) [inline], [private]
12.34.2.19 void seq64::mainwnd::update_window_title( ) [private]
```

Note that the name of the application is obtained by the "(SEQ64 PACKAGE)" construction.

The format of the caption bar is the name of the package/application, followed by the file-specification (shortened if necessary so that the name of the file itself can be seen), ending with the PPQN value in parentheses.

```
12.34.2.20 void seq64::mainwnd::file_new( ) [inline], [private]

12.34.2.21 void seq64::mainwnd::file_open( ) [inline], [private]

12.34.2.22 void seq64::mainwnd::file_save( ) [inline], [private]

12.34.2.23 void seq64::mainwnd::file_save( ) [inline], [private]

12.34.2.24 void seq64::mainwnd::set_song_mute( perform::mute_op_t op ) [inline], [private]

12.34.2.25 void seq64::mainwnd::file_import_dialog( ) [private]
```

Note that every track of the MIDI file will be imported, even if the track is only a label track (without any MIDI events), or a very long track.

The main difference between the Open operation and the Import operation seems to be that the latter can read MIDI files into a screen-set greater than screen-set 0. No, that's not true, so far. No matter what the current screen-set setting, the import is appended after the current data in screen-set 0. Then, if it overflows that screen-set, the overflow goes into the next screen-set.

It might be nice to have the option of importing a MIDI file into a specific screen-set, for better organization, as well as being able to offset the sequence number.

Also, it is important to note that perf().clear_all() is not called by this routine, as we are merely adding to what might already be there.

```
12.34.2.26 void seq64::mainwnd::options_dialog( ) [private]
12.34.2.27 void seq64::mainwnd::about_dialog( ) [private]
```

I (Chris) took the liberty of tacking my name at the end, and hope to have done eventually enough work to warrant having it there.

```
12.34.2.28 int seq64::mainwnd::query_save_changes( ) [private]
12.34.2.29 void seq64::mainwnd::new_open_error_dialog( ) [private]
12.34.2.30 void seq64::mainwnd::file_save_as(bool do_export = false) [private]
```

Please note that Sequencer64 will not adopt the "c_seq32_midi" type of file, because it already saves its files in a format that other sequencers should be able to read.

Stazed on the intent of the export functionality:

The original intent was to be able to play an exported song in something like TiMIDIty. After I completed things I realized that there could be an editing benefit as well. I like to record from my MIDI keyboard, improvised to a drum beat, on a long sequence (64 measures). Some is junk, but there are usually parts that I can use. In original seq24, to cut out the good or bad stuff, you would have to search the sequence by listening, then cut and move or copy and paste to a new sequence. It could be done but was always tedious. The paste box for the sequence sometimes made it difficult to find the correct note location, measure, and beat. Also, on a long sequence, you need to zoom out to see the copy location as it played, but zoom in for the precise paste location. In addition if you wanted to change the measure of the notes, it became a trial and error of copy/paste, listen, move, listen, move....

With the added Song editor feature of split trigger to mouse and copy paste trigger to mouse, you can now do all the editing from the song editor. Listen to the sequence, cut out the good or bad parts and reassemble. Move or copy all good trigger parts to the left start and delete all the bad stuff. Now you can use the song export to create the new sequence. Just mute all other tracks and export. Re-import and the new cleaned sequence is already done. Also I use it for importing drum beats from a single '32/'42 file that contains dozens of different styles with intros and endings. I like to sync two instances of '32 or '42 together with jack, then play/experiment with the different beats. If I find something I like, create the song trigger for the part I like in the drum file, export and import.

I actually do not use the song export for anything but editing.

Note that the split trigger variant of Stazed, where it doesn't just split the section in half, is not yet implemented (2016-08-05).

Parameters

do_export	If true, then just write out the file and don't change the name of the current file based on the
	file-name the user selected. The default value of this parameter is false.

```
12.34.2.31 void seq64::mainwnd::file_exit( ) [private]
12.34.2.32 void seq64::mainwnd::new_file( ) [private]
```

Not sure that we need to clear the modified flag here, especially since it is now centralizeed in the perform object. Let perf().clear_all() handle it now.

```
12.34.2.33 bool seq64::mainwnd::save_file() [private]
```

Here we specify the current value of m_ppqn, which was set when reading the MIDI file. We also let midifile tell the perform that saving worked, so that the "is modified" flag can be cleared. The midifile class is already a friend of perform.

```
12.34.2.34 void seq64::mainwnd::choose_file( ) [private]
12.34.2.35 bool seq64::mainwnd::is_save( ) [private]
12.34.2.36 bool seq64::mainwnd::install_signal_handlers( ) [private]
12.34.2.37 bool seq64::mainwnd::signal_action(Glib::IOCondition condition) [private]
```

Returns

Returns true if the signalling was able to be completed, even if it was an unexpected signal.

```
12.34.2.38 bool seq64::mainwnd::on_delete_event ( GdkEventAny * ev ) [private]
```

Any changed data is saved. If the pattern is playing, then it is stopped. We now use perform::is_pattern_playing().

```
12.34.2.39 bool seq64::mainwnd::on_key_press_event( GdkEventKey * ev ) [private]
```

It also handles the control-key and modifier-key combinations matching the entries in its list of if statements.

Also, we now effectively press the CAPS LOCK key for the user if in group-learn mode, via the keystroke::shift_lock() function.

```
12.34.2.40 bool seq64::mainwnd::on_key_release_event ( GdkEventKey * ev ) [private]
```

Is this worth turning into a switch statement? Or offloading to a perform member function? The latter.

Also, we now effectively press the CAPS LOCK key for the user if in group-learn mode.

Todo Test this functionality in old and new application.

Returns

Always returns false. This matches seq24 behavior.

```
12.34.2.41 void seq64::mainwnd::on_grouplearnchange(bool state) [private], [virtual]
```

This handler responds to a learn-mode change from perf().

Reimplemented from seq64::performcallback.

12.34.3 Field Documentation

```
12.34.3.1 int seq64::mainwnd::m_sigpipe [static], [private]
```

This static member provides a couple of pipes for signalling/messaging.

```
12.34.3.2 Gtk::Tooltips* seq64::mainwnd::m_tooltips [private]
```

12.34.3.3 Gtk::MenuBar* seq64::mainwnd::m_menubar [private]

The whole menu bar.

```
12.34.3.4 Gtk::Menu* seq64::mainwnd::m_menu_file [private]
```

12.34.3.5 Gtk::Menu* seq64::mainwnd::m_menu_edit [private]

12.34.3.6 Gtk::Menu* seq64::mainwnd::m_menu_view [private]

12.34.3.7 Gtk::Menu* seq64::mainwnd::m_menu_help [private]

12.34.3.8 int seq64::mainwnd::m_ppqn [private]

We need it early here to be able to pass it along to child objects.

```
12.34.3.9 mainwid* seq64::mainwnd::m_main_wid [private]
```

The first is the Patterns Panel, which the mainwid helps implement. We end up sharing this object with perfedit, perfnames, and seqedit in order to allow the seqedit object to notify the mainwid (indirectly) of the currently-edited sequence.

```
12.34.3.10 maintime* seq64::mainwnd::m_main_time [private]
```

12.34.3.11 perfedit* seq64::mainwnd::m_perf_edit [private]

12.34.3.12 perfedit* seq64::mainwnd::m_perf_edit_2 [private]

The second makes it easy to line up two different patterns that cannot be seen together on one performance editor.

```
12.34.3.13 options* seq64::mainwnd::m_options [private]
12.34.3.14 Gdk::Cursor seq64::mainwnd::m_main_cursor [private]
12.34.3.15 Gtk::lmage* seq64::mainwnd::m_image_play [private]
12.34.3.16 Gtk::Button* seq64::mainwnd::m_button_learn [private]
12.34.3.17 Gtk::Button* seq64::mainwnd::m_button_stop [private]
12.34.3.18 Gtk::Button* seq64::mainwnd::m_button_play [private]
If configured to support pause, it also supports the pause pixmap and functionality.
12.34.3.19 Gtk::Button* seq64::mainwnd::m_button_perfedit [private]
12.34.3.20 Gtk::Adjustment* seq64::mainwnd::m_adjust_bpm [private]
BPM adjustment object.
12.34.3.21 Gtk::SpinButton* seq64::mainwnd::m_spinbutton_bpm [private]
12.34.3.22 Gtk::Adjustment* seq64::mainwnd::m_adjust_ss [private]
Screenset adjustment.
12.34.3.23 Gtk::SpinButton* seq64::mainwnd::m_spinbutton_ss [private]
12.34.3.24 Gtk::Adjustment* seq64::mainwnd::m_adjust_load_offset [private]
These controls are used in the File / Import dialog to change where the imported file will be loaded in the sequences
space, which ranges from 0 to 1024 in blocks of 32 patterns. Load number for import.
12.34.3.25 Gtk::SpinButton*seq64::mainwnd::m_spinbutton_load_offset [private]
12.34.3.26 Gtk::Entry* seq64::mainwnd::m_entry_notes [private]
```

This is just a long text-edit field that can be used to enter a long name or a short description of the current screenset.

```
12.34.3.28 sigc::connection seq64::mainwnd::m_timeout_connect [private]

12.34.3.29 bool seq64::mainwnd::m_menu_mode [private]

This is a "stazed" feature that might be generally useful.

12.34.3.30 bool seq64::mainwnd::m_call_seq_edit [private]

Currently, the hard-wired key for this function is the equals key.

12.34.3.31 bool seq64::mainwnd::m_call_seq_eventedit [private]
```

12.35 seq64::mastermidibus Class Reference

Currently, the hard-wired key for this function is the minus key.

The class that "supervises" all of the midibus objects?

Public Member Functions

• mastermidibus (int ppqn=SEQ64_USE_DEFAULT_PPQN, int bpm=c_beats_per_minute)

The mastermidibus default constructor fills the array with our busses.

∼mastermidibus ()

The destructor deletes all of the output busses, clears out the ALSA events, stops and frees the queue, and closes ALSA for this application.

• void init (int ppqn)

Initialize the mastermidibus.

snd_seq_t * get_alsa_seq () const

'Getter' function for member m_alsa_seq

int get_num_out_buses () const

'Getter' function for member m_num_out_buses

• int get_num_in_buses () const

'Getter' function for member m_num_in_buses

void set_beats_per_minute (int bpm)

Set the BPM value (beats per minute).

void set_ppqn (int ppqn)

Set the PPQN value (parts per quarter note).

• bool filter_by_channel () const

'Getter' function for member m_filter_by_channel

void filter_by_channel (bool flag)

'Setter' function for member m_filter_by_channel

• int get beats per minute () const

'Getter' function for member m_beats_per_minute

int get_ppqn () const

'Getter' function for member m_ppqn

std::string get_midi_out_bus_name (int bus)

Get the MIDI output buss name for the given (legal) buss number.

std::string get_midi_in_bus_name (int bus)

Get the MIDI input buss name for the given (legal) buss number.

void print ()

Print some information about the available MIDI output busses.

• void flush ()

Flushes our local queue events out into ALSA.

· void start ()

Starts all of the configured output busses up to m_num_out_buses.

• void stop ()

Stops each of the output busses.

void clock (midipulse tick)

Generates the MIDI clock for each of the output busses.

void continue_from (midipulse tick)

Gets the output busses running again, if ALSA support is enabled.

void init clock (midipulse tick)

Initializes the clock of each of the output busses.

• int poll for midi ()

Initiate a poll() on the existing poll descriptors.

bool is_more_input ()

Test the ALSA sequencer to see if any more input is pending.

• bool get_midi_event (event *in)

Grab a MIDI event.

void set_sequence_input (bool state, sequence *seq)

Set the input sequence object, and set the $m_dumping_input$ value to the given state.

void dump_midi_input (event in)

This function augments the recording functionality by looking for a sequence that has a matching channel number, logging the event to that sequence, and then immediately exiting.

• bool is dumping () const

'Getter' function for member m_dumping_input

• sequence * get_sequence () const

'Getter' function for member m_seq

void sysex (event *event)

Handle the sending of SYSEX events.

void port_start (int client, int port)

Start the given ALSA MIDI port.

void port_exit (int client, int port)

Turn off the given port for the given client.

void play (bussbyte bus, event *e24, midibyte channel)

Handle the playing of MIDI events on the MIDI buss given by the parameter, as long as it is a legal buss number.

void set_clock (bussbyte bus, clock_e clock_type)

Set the clock for the given (legal) buss number.

clock_e get_clock (bussbyte bus)

Gets the clock setting for the given (legal) buss number.

void set_input (bussbyte bus, bool inputing)

Set the status of the given input buss, if a legal buss number.

bool get_input (bussbyte bus)

Get the input for the given (legal) buss number.

Private Attributes

snd_seq_t * m_alsa_seq

The ALSA sequencer client handle.

int m_max_busses

The maximum number of busses supported.

• int m num out buses

The number of output busses.

• int m_num_in_buses

The number of input busses.

midibus * m_buses_out [c_max_busses]

Output MIDI busses.

• midibus * m_buses_in [c_max_busses]

Input MIDI busses.

• midibus * m_bus_announce

MIDI buss announcer?

bool m_buses_out_active [c_max_busses]

Active output MIDI busses.

bool m_buses_in_active [c_max_busses]

Active input MIDI busses.

• bool m_buses_out_init [c_max_busses]

Output MIDI buss initialization.

bool m_buses_in_init [c_max_busses]

Input MIDI buss initialization.

clock_e m_init_clock [c_max_busses]

Clock initialization.

• bool m_init_input [c_max_busses]

Input initialization?

• int m_queue

The ID of the MIDI queue.

• int m ppqn

Resolution in parts per quarter note.

int m_beats_per_minute

BPM (beats per minute).

• int m_num_poll_descriptors

The number of descriptors for polling.

• struct pollfd * m_poll_descriptors

Points to the list of descriptors for polling.

• bool m_dumping_input

For dumping MIDI input to a sequence for recording.

• std::vector< sequence * > m_vector_sequence

Used for the new "stazed" feature of filtering MIDI channels so that a sequence gets only the channels meant for it.

bool m_filter_by_channel

If true, the m_vector_sequence container is used to divert incoming data to the sequence that has the channel it is meant for.

• sequence * m_seq

Points to the sequence object.

• mutex m_mutex

The locking mutex.

12.35.1 Constructor & Destructor Documentation

12.35.1.1 seq64::mastermidibus::mastermidibus (int ppqn = SEQ64_USE_DEFAULT_PPQN, int bpm = c_beats_per_minute)

Parameters

ppqn	Provides the PPQN value for this object. However, in most cases, the default, SEQ64_USE_DEFAULT_PPQN should be specified. Then the caller of this constructor should call mastermidibus::set_ppqn() to set up the proper PPQN value.	
bpm	Provides the beats per minute value, which defaults to c_beats_per_minute.	

12.35.1.2 seg64::mastermidibus::~mastermidibus()

Valgrind indicates we might have issues caused by the following functions:

```
- snd_config_hook_load()
- snd_config_update_r() via snd_seq_open()
- _dl_init() and other GNU function
- init_gtkmm_internals() [version 2.4]
```

12.35.2 Member Function Documentation

12.35.2.1 void seq64::mastermidibus::init (int ppqn)

It initializes 16 MIDI output busses, a hardwired constant, SEQ64_ALSA_OUTPUT_BUSS_MAX == 16. Only one MIDI input buss is initialized.

Parameters

ppqn	The PPQN value to which to initialize the master MIDI buss.
------	---

```
12.35.2.2 snd_seq_t* seq64::mastermidibus::get_alsa_seq( ) const [inline]
12.35.2.3 int seq64::mastermidibus::get_num_out_buses( ) const [inline]
12.35.2.4 int seq64::mastermidibus::get_num_in_buses( ) const [inline]
12.35.2.5 void seq64::mastermidibus::set_beats_per_minute( int bpm )
```

This is done by creating an ALSA tempo structure, adding tempo information to it, and then setting the ALSA sequencer object with this information.

We fill the ALSA tempo structure (snd_seq_queue_tempo_t) with the current tempo information, set the BPM value, put it in the tempo structure, and give the tempo value to the ALSA queue.

Threadsafe

Parameters

	Provides the beats-per-minute value to set.
hnm	Drovides the bests per minute value to set
DUIII	riovides the beats-ber-minute value to set.

```
12.35.2.6 void seq64::mastermidibus::set_ppqn ( int ppqn )
```

This is done by creating an ALSA tempo structure, adding tempo information to it, and then setting the ALSA sequencer object with this information. Fills the tempo structure with the current tempo information. Then sets the ppqn value. Finally, gives the tempo structure to the ALSA queue.

Threadsafe

Parameters

ppqn The PPQN va	alue to be set.
------------------	-----------------

```
12.35.2.7 bool seq64::mastermidibus::filter_by_channel() const [inline]

12.35.2.8 void seq64::mastermidibus::filter_by_channel(bool flag) [inline]

12.35.2.9 int seq64::mastermidibus::get_beats_per_minute() const [inline]

12.35.2.10 int seq64::mastermidibus::get_ppqn() const [inline]

12.35.2.11 std::string seq64::mastermidibus::get_midi_out_bus_name(int bus)

Parameters
```

bus Provides the output buss number. Checked before usage.

Returns

Returns the buss name as a standard C++ string, truncated to 80-1 characters. Also contains an indication that the buss is disconnected or unconnected. If the buss number is illegal, this string is empty.

12.35.2.12 std::string seq64::mastermidibus::get_midi_in_bus_name (int bus)

Parameters

bus Provides the input buss number.

Returns

Returns the buss name as a standard C++ string, truncated to 80-1 characters. Also contains an indication that the buss is disconnected or unconnected.

```
12.35.2.13 void seq64::mastermidibus::print ( )
12.35.2.14 void seq64::mastermidibus::flush ( )
```

Threadsafe

```
12.35.2.15 void seq64::mastermidibus::start ( )
Threadsafe
12.35.2.16 void seq64::mastermidibus::stop ( )
If ALSA support is enable, also drains the output, synchronizes the output queue, and then stop the queue.
Threadsafe
12.35.2.17 void seq64::mastermidibus::clock ( midipulse tick )
Threadsafe
Parameters
        Provides the tick value with which to set the buss clock.
12.35.2.18 void seq64::mastermidibus::continue_from ( midipulse tick )
Threadsafe
Parameters
        Provides the tick value to continue from.
12.35.2.19 void seq64::mastermidibus::init_clock ( midipulse tick )
Threadsafe
Parameters
        Provides the tick value with which to initialize the buss clock.
12.35.2.20 int seq64::mastermidibus::poll_for_midi( )
Returns
      Returns the result of the poll, or 0 if ALSA is not supported.
12.35.2.21 bool seq64::mastermidibus::is_more_input()
Threadsafe
```

Returns

Returns true if ALSA is supported, and the returned size is greater than 0, or false otherwise.

12.35.2.22 bool seq64::mastermidibus::get_midi_event (event * inev)

First, a rather large buffer is allocated on the stack to hold the MIDI event data. Next, if the –alsa-manual-ports option is not in force, then we check to see if the event is a port-start, port-exit, or port-change event, and we process it, and are done.

Otherwise, we create a "MIDI event parser" and decode the MIDI event.

Threadsafe

Parameters

inev The event to be set based or	n the found input event.
-----------------------------------	--------------------------

We will only get EVENT_SYSEX on the first packet of MIDI data; the rest we have to poll for. SysEx processing is currently disabled.

12.35.2.23 void seq64::mastermidibus::set_sequence_input (bool state, sequence * seq)

Threadsafe

Parameters

state	Provides the dumping-input (recording) state to be set.	
seq	7	
	a null pointer, to disable the sequence setting.	

12.35.2.24 void seq64::mastermidibus::dump_midi_input (event ev)

Parameters

ev T	The event that was recorded, passed as a copy.
------	--

12.35.2.25 bool seq64::mastermidibus::is_dumping() const [inline]

12.35.2.26 sequence* seq64::mastermidibus::get_sequence() const [inline]

12.35.2.27 void seq64::mastermidibus::sysex (event * ev)

The event is sent to all MIDI output busses.

Threadsafe

12.35.2.28 void seq64::mastermidibus::port_start (int *client*, int *port*)

Threadsafe Quite a lot is done during the lock!

Parameters

client	Provides the ALSA client number.
port	Provides the ALSA client port.

12.35.2.29 void seq64::mastermidibus::port_exit (int client, int port)

Both the input and output busses for the given client are stopped, and set to inactive.

Threadsafe

Parameters

client	The client to be matched and acted on.	
port	The port to be acted on. Both parameter must be match before the buss is made inactive.	

12.35.2.30 void seq64::mastermidibus::play (bussbyte bus, event * e24, midibyte channel)

Threadsafe

Parameters

bus	The buss to start play on. Ooh, we just noticed that value should be checked before usage	
e24	The seq24 event to play on the buss.	
channel The channel on which to play the event.		

12.35.2.31 void seq64::mastermidibus::set_clock (bussbyte bus, clock_e clocktype)

The legality checks are a little loose, however.

Threadsafe

Parameters

bus	The buss to start play on. Checked before usage.	
clocktype	The type of clock to be set, either "off", "pos", or "mod", as noted in the midibus_common module.	

12.35.2.32 clock_e seq64::mastermidibus::get_clock (bussbyte bus)

Parameters

bus	Provides the buss number to read. Checked before usage.
-----	---

Returns

If the buss number is legal, and the buss is active, then its clock setting is returned. Otherwise, e_clock_off is returned.

12.35.2.33 void seq64::mastermidibus::set_input (bussbyte bus, bool inputing)

Why is another buss-count constant, and a global one at that, being used? And I thought there was only one input buss anyway! Well, there is only one ALSA input buss, but more can be used with JACK, apparently.

Threadsafe

Parameters

bus	Provides the buss number.
inputing	True if the input bus will be inputting MIDI data.

12.35.2.34 bool seq64::mastermidibus::get_input (bussbyte bus)

Parameters

bus	Provides the buss number.

Returns

Always returns false.

12.35.3 Field Documentation

12.35.3.1 snd_seq_t* seq64::mastermidibus::m_alsa_seq [private]

12.35.3.2 int seq64::mastermidibus::m_max_busses [private]

Set to c max busses for now.

12.35.3.3 int seq64::mastermidibus::m_num_out_buses [private]

12.35.3.4 int seq64::mastermidibus::m_num_in_buses [private]


```
12.35.3.5 midibus* seq64::mastermidibus::m_buses_out[c_max_busses] [private]
12.35.3.6 midibus* seq64::mastermidibus::m_buses_in[c_max_busses] [private]
12.35.3.7 midibus* seq64::mastermidibus::m_bus_announce [private]
12.35.3.8 bool seq64::mastermidibus::m buses out active[c max busses] [private]
12.35.3.9 bool seq64::mastermidibus::m_buses_in_active[c_max_busses] [private]
12.35.3.10 bool seq64::mastermidibus::m buses out init[c max busses] [private]
12.35.3.11 bool seq64::mastermidibus::m_buses_in_init[c_max_busses] [private]
12.35.3.12 clock e seq64::mastermidibus::m_init_clock[c max busses] [private]
12.35.3.13 bool seq64::mastermidibus::m_init_input[c_max_busses] [private]
12.35.3.14 int seq64::mastermidibus::m_queue [private]
12.35.3.15 int seq64::mastermidibus::m_ppqn [private]
12.35.3.16 int seq64::mastermidibus::m_beats_per_minute [private]
We had to lengthen this name; way too easy to confuse it with "bpm" for "beats per measure".
12.35.3.17 int seq64::mastermidibus::m_num_poll_descriptors [private]
12.35.3.18 struct pollfd* seq64::mastermidibus::m_poll_descriptors [private]
12.35.3.19 bool seq64::mastermidibus::m_dumping_input [private]
12.35.3.20 std::vector<sequence *> seq64::mastermidibus::m_vector_sequence [private]
We want to make this a run-time, non-legacy option.
12.35.3.21 bool seq64::mastermidibus::m_filter_by_channel [private]
12.35.3.22 sequence* seq64::mastermidibus::m_seq [private]
12.35.3.23 mutex seq64::mastermidibus::m_mutex [private]
```

This object is passed to an automutex object that lends exception-safety to the mutex locking.

12.36 seq64::midi_container Class Reference

This class is the abstract base class for a container of MIDI track information.

Inheritance diagram for seq64::midi container:



Public Member Functions

• midi_container (sequence &seq)

Fills in the few members of this class.

virtual ∼midi container ()

A rote constructor needed for a base class.

void fill (int tracknumber, const perform &p)

This function fills the given track (sequence) with MIDI data from the current sequence, preparatory to writing it to a file.

• virtual std::size_t size () const

Returns the size of the container, in midibytes.

• virtual bool done () const

Instead of checking for the size of the container when "emptying" it [see the midifile::write() function], use this function, which is overridden to match the type of container being used.

virtual void put (midibyte b)=0

Provides a way to add a MIDI byte into the container.

• virtual midibyte get () const =0

Provide a way to get the next byte from the container.

virtual void clear ()=0

Provides a way to clear the container.

Protected Member Functions

· unsigned int position_reset () const

'Setter' function for member m_position_for_get Sets the position to 0 and then returns that value.

· unsigned int position () const

'Getter' function for member m_position_for_get Returns the current position.

void position_increment () const

'Getter' function for member m_position_for_get Increments the current position.

Private Member Functions

• void add_variable (midipulse v)

This function masks off the lower 8 bits of the long parameter, then shifts it right 7, and, if there are still set bits, it encodes it into the buffer in reverse order.

void add long (midipulse x)

Adds a long value (a MIDI pulse/tick value) to the container.

void add_short (midishort x)

Adds a short value (two bytes) to the container.

void add_event (const event &e, midipulse deltatime)

Adds an event to the container.

• void fill_seq_number (int seq)

Fills in the sequence number.

void fill seq name (const std::string &name)

Fills in the sequence name.

- void fill_meta_track_end (midipulse deltatime)
- void fill proprietary ()

Fills in the Sequencer64-specific information for the current sequence: The MIDI buss number, the time-signature, and the MIDI channel.

void fill_time_sig_and_tempo (const perform &p)

Fill in the time-signature and tempo information.

midipulse song_fill_seq_event (const trigger &trig, midipulse prev_timestamp)

Fills in sequence events based on the trigger and events in the sequence associated with this midi container.

void song_fill_seq_trigger (const trigger &trig, midipulse len, midipulse prev_timestamp)

Fills in the trigger for the whole sequence.

Private Attributes

• sequence & m_sequence

Provide a hook into a sequence so that we can exchange data with a sequence object.

unsigned int m_position_for_get

Provides the position in the container when making a series of get() calls on the container.

Friends

· class midifile

12.36.1 Detailed Description

It is the base class for midi_list and midi_vector.

12.36.2 Constructor & Destructor Documentation

12.36.2.1 seq64::midi_container::midi_container (sequence & seq)

Parameters

seq Provides a reference to the sequence/track for which this container holds MIDI data.

```
12.36.2.2 virtual seq64::midi_container::~midi_container( ) [inline], [virtual]
```

12.36.3 Member Function Documentation

12.36.3.1 void seq64::midi_container::fill (int tracknumber, const perform & p)

Note that some of the events might not come out in the same order they were stored in (we see that with program-change events). This function replaces sequence::fill list().

Now, for sequence 0, an alternate format for writing the sequencer number chunk is "FF 00 00". But that format can only occur in the first track, and the rest of the tracks then don't need a sequence number, since it is assumed to increment. This application doesn't use that shortcut.

Stazed:

```
The "stazed" (seq32) code implements a function like this one using a function sequence::fill_proprietary_list() that we don't need for our implementation... it is part of our midi_container::fill() function.
```

Triggers:

```
Triggers are added by first calling add_variable(0), which is needed because why? Then 0xFF 0x7F is written, followed by the length value, which is the number of triggers at 3 long integers per trigger, plus the 4-byte code for triggers, c_triggers_new = 0x24240008.
```

Not threadsafe The sequence object bound to this container needs to provide the locking mechanism when calling this function.

tracknumber	Provides the track number. This number is masked into the track information.
lidomination	Trovided the track number. This number is masked into the track information.

To allow other sequencers to read Seq24/Sequencer64 files, we should provide the Time Signature and Tempo meta events, in the 0th (first) track (sequence). These events must precede any "real" MIDI events. They are not included if the legacy-format option is in force.

```
12.36.3.2 virtual std::size_t seq64::midi_container::size( ) const [inline], [virtual]
Must be overridden in the derived class, though not pure.
Reimplemented in seq64::midi list, and seq64::midi vector.
12.36.3.3 virtual bool seq64::midi_container::done( ) const [inline], [virtual]
Reimplemented in seq64::midi_vector, and seq64::midi_list.
12.36.3.4 virtual void seq64::midi_container::put( midibyte b) [pure virtual]
The original seq24 container used an std::list and a push front operation.
Implemented in seq64::midi_vector, and seq64::midi_list.
12.36.3.5 virtual midibyte seq64::midi_container::get( ) const [pure virtual]
It also increments m_position_for_get.
Implemented in seq64::midi_vector, and seq64::midi_list.
12.36.3.6 virtual void seq64::midi_container::clear( ) [pure virtual]
Implemented in seq64::midi_vector, and seq64::midi_list.
12.36.3.7 unsigned int seq64::midi_container::position_reset( ) const [inline], [protected]
12.36.3.8 unsigned int seq64::midi_container::position() const [inline], [protected]
12.36.3.9 void seq64::midi_container::position_increment( ) const [inline], [protected]
12.36.3.10 void seq64::midi_container::add_variable( midipulse v ) [private]
This function "replaces" sequence::add list var().
```

v The data value to be added to the current event in the MIDI container.

12.36.3.11 void seq64::midi_container::add_long(midipulse x) [private]

What is the difference between this function and add_list_var()? This function "replaces" sequence::add_long_list(). This was a *global* internal function called addLongList(). Let's at least make it a private member now, and hew to the naming conventions of this class.

Parameters

x Provides the timestamp (pulse value) to be added to the container.

12.36.3.12 void seq64::midi_container::add_short(midishort x) [private]

Parameters

x Provides the timestamp (pulse value) to be added to the container.

12.36.3.13 void seq64::midi_container::add_event (const event & e, midipulse deltatime) [private]

If the sequence's MIDI channel is EVENT_NULL_CHANNEL == 0xFF, then it is the copy of an SMF 0 sequence that the midi_splitter created. We want to be able to save it along with the other tracks, but won't be able to read it back if all the channels are bad. So we just use the channel from the event.

12.36.3.14 void seq64::midi_container::fill_seq_number(int seq) [private]

Writes 0xFF 0x00 0x02, and then the number. This function is used in the new midifile::write_song() function, which should be ready to go by the time you're reading this.

Compare this function to the beginning of midi_container::fill().

Parameters

seq The sequence/track number to write.

12.36.3.15 void seq64::midi_container::fill_seq_name(const std::string & name) [private]

Writes 0xFF 0x03, and then the track name. This function is used in the new midifile::write_song() function, which should be ready to go by the time you're reading this.

Compare this function to the beginning of midi_container::fill().

name	The sequence/track name to set. We could get this item from m_sequence, but the parameter allows
	the flexibility to change the name.

12.36.3.16 void seq64::midi_container::fill_meta_track_end (midipulse deltatime) [private]

12.36.3.17 void seq64::midi_container::fill_proprietary() [private]

Then, if we're not using the legacy output format, we add the "events" for the musical key, musical scale, and the background sequence for the current sequence. Finally, if tranpose support has been compiled into the program, we add that information as well. New feature: save more sequence-specific values, if not legacy format and not saved globally. We use a single byte for the key and scale, and a long for the background sequence. We save these values only if they are different from the defaults; in most cases they will have been left alone by the user. We save per-sequence values here only if the global-background-sequence feature is not in force.

12.36.3.18 void seq64::midi_container::fill_time_sig_and_tempo(const perform & p) [private]

This function is used only for the first track, The sizes of these meta events are defined as SEQ64_TIME_TEMP← O_SIZE. However, we do not have to add that value in, as it is already counted in the intrinsic size of the container.

We now make sure that the proper values are part of the perform object for usage in this particular track. For export, we cannot guarantee that the first (0th) track/sequence is exportable.

Parameters

p Provides the performance object from which we get some global MIDI parameters.

12.36.3.19 midipulse seq64::midi_container::song_fill_seq_event (const trigger & trig, midipulse prev_timestamp) [private]

Parameters

trig	The current trigger to be processed.
prev_timestamp	The time-stamp of the previous event.

Returns

The next time-stamp value is returned.

12.36.3.20 void seq64::midi_container::song_fill_seq_trigger (const trigger & trig, midipulse length, midipulse prev_timestamp) [private]

For a song-performance, there will be only one trigger, covering the beginning to the end of the fully unlooped track.

trig	The current trigger to be processed.
length	Provides the total length of the sequence.
prev_timestamp	The time-stamp of the previous event, which is actually the first event.

12.36.4 Friends And Related Function Documentation

12.36.4.1 friend class midifile [friend]

12.36.5 Field Documentation

12.36.5.1 sequence& **seq64**::midi_container::m_sequence [private]

12.36.5.2 unsigned int seq64::midi_container::m_position_for_get [mutable], [private]

12.37 seq64::midi_control Class Reference

This class (formerly a struct) contains the control information for sequences that make up a live set.

Public Member Functions

• midi_control ()

This default constructor creates a "zero" object.

- bool active () const
- bool inverse_active () const
- · int status () const
- int data () const
- int min_value () const
- int max_value () const
- void set (int values[6])

Not so sure if this really saves trouble for the caller.

• void set (midibyte values[6])

Not so sure if this really saves trouble for the caller.

· bool match (midibyte status, midibyte data) const

Handles a common check in the perform module.

• bool in_range (midibyte data) const

Handles a common check in the perform module.

Private Attributes

· bool m active

Provides the value for active.

· bool m inverse active

Provides the value for inverse-active.

· int m status

Provides the value for the status.

int m data

Provides the value for the data.

· int m_min_value

Provides the minimum value for the controller.

• int m_max_value

Provides the value for the controller.

12.37.1 Detailed Description

Note that, although we've converted this to a full-fledged class, the ordering of variables and the data arrays used to fill them is very significant. See the midifile and optionsfile modules.

The perform module sets up the three following arrays for each of the MIDI controls that can be defined in the "rc" file:

```
m_midi_cc_toggle[]
m_midi_cc_on[]
m_midi_cc_off[]
```

These three arrays are specified in the "rc" by a line like the following:

```
n [0 0 0 0 0 0] [0 0 0 0 0] [0 0 0 0 0]
```

where n ranges from 0 to 73. Lines 0 to 31 provide controller values for the "pattern group", one line for each of the 32 pattern slots. Lines 32 to 63 provide controller values for the "mute in group", one line for each of the 32 pattern slots. The rest of the lines provide entries for control of:

BPM up, BPM down, Screen-set up, Screen-set down, Mod Replaces, Mod Snapshot, Mod Queue, Mod gmute (group mute), Mod glearn (group learn), and Screen-set Play.

In each of the bracketed sections, the values correspond to the members in this order: m_active , $m_inverse_active$, m_status , m_data , m_min_value , and m_max_value .

Why are the status, data, and \min/\max values long? A character or midibyte would be enough. We'll fix that later, once we have tested this stuff. We do need to convert them from long to int, though, and do that in the scanning and output done by optionsfile.

12.37.2 Constructor & Destructor Documentation

```
12.37.2.1 seq64::midi_control::midi_control() [inline]
```

Every member is either false or zero.

12.37.3 Member Function Documentation

```
12.37.3.1 bool seq64::midi_control::active() const [inline]

12.37.3.2 bool seq64::midi_control::inverse_active() const [inline]

12.37.3.3 int seq64::midi_control::status() const [inline]

12.37.3.4 int seq64::midi_control::data() const [inline]

12.37.3.5 int seq64::midi_control::min_value() const [inline]

12.37.3.6 int seq64::midi_control::max_value() const [inline]
```

12.37.3.7 void seq64::midi_control::set(int values[6]) [inline]

It fits in with the big-ass sscanf() call in optionsfile.

Parameters

values	Provides the six values, in an integer array, to set into the members in this order: m_active,
	m_inverse_active, m_status, m_data, m_min_value, and m_max_value.

12.37.3.8 void seq64::midi_control::set (midibyte values[6]) [inline]

It fits in with the usage in midifile.

Parameters

ſ	values	Provides the six values, in a byte array, to set into the members in this order: m_active, m_inverse_active,
		m_status, m_data, m_min_value, and m_max_value.

12.37.3.9 bool seq64::midi_control::match (midibyte status, midibyte data) const [inline]

Parameters

status	Provides the status byte, which is checked against m_status.
data	Provides the data byte, which is checked against m_data.

12.37.3.10 bool seq64::midi_control::in_range (midibyte data) const [inline]

12.37.4 Field Documentation

12.37.4.1 bool seq64::midi_control::m_active [private]

12.37.4.2	<pre>bool seq64::midi_control::m_inverse_active [private]</pre>
12.37.4.3	<pre>int seq64::midi_control::m_status [private]</pre>
12.37.4.4	<pre>int seq64::midi_control::m_data [private]</pre>
12.37.4.5	<pre>int seq64::midi_control::m_min_value [private]</pre>
12.37.4.6	<pre>int seq64::midi_control::m_max_value [private]</pre>
12.38	seq64::midi_list Class Reference

This class is the std::list implementation of the midi_container.

Inheritance diagram for seq64::midi_list:



Public Member Functions

• midi_list (sequence &seq)

This constructor fills in the members.

virtual ∼midi_list ()

A rote constructor needed for a base class.

• virtual std::size_t size () const

Returns the size of the container, in midibytes.

• virtual bool done () const

For popping data from the MIDI list, we are done when the container is empty.

• virtual void put (midibyte b)

Provides a way to add a MIDI byte into the list.

• virtual midibyte get () const

Provide a way to get the next byte from the container.

· virtual void clear ()

Provides a way to clear the container.

Private Types

 $\bullet \ \ typedef \ std:: list < midibyte > CharList$

Provides the type of this container.

Private Attributes

· CharList m_char_list

The container itself.

Additional Inherited Members

12.38.1 Member Typedef Documentation

```
12.38.1.1 typedef std::list<midibyte> seq64::midi_list::CharList [private]
```

This type is basically the same as the midifile::m_char_list container in the midifile module.

12.38.2 Constructor & Destructor Documentation

```
12.38.2.1 seq64::midi_list::midi_list ( sequence & seq )
```

Parameters

```
seq The sequence/track object that is using this container.
```

```
12.38.2.2 virtual seq64::midi_list::~midi_list() [inline], [virtual]
```

12.38.3 Member Function Documentation

```
12.38.3.1 virtual std::size_t seq64::midi_list::size( ) const [inline], [virtual]
```

Reimplemented from seq64::midi_container.

```
12.38.3.2 virtual bool seq64::midi_list::done() const [inline], [virtual]
```

Reimplemented from seq64::midi container.

```
12.38.3.3 virtual void seq64::midi_list::put( midibyte b) [inline], [virtual]
```

The original seq24 list used an std::list and a push front operation.

Implements seq64::midi container.

```
12.38.3.4 virtual midibyte seq64::midi_list::get( ) const [inline], [virtual]
```

In this implementation, m_position_for_get is not used. The elements of the container are popped off backward! This modifies the character list, so it has to be mutable.

Implements seq64::midi_container.

```
12.38.3.5 virtual void seq64::midi_list::clear( ) [inline], [virtual]
```

Implements seq64::midi_container.

12.38.4 Field Documentation

```
12.38.4.1 CharList seq64::midi_list::m_char_list [mutable], [private]
```

It has to be mutable because the const-function get() actually modifies the container when getting a byte.

12.39 seg64::midi_measures Class Reference

Provides a data structure to hold the numeric equivalent of the measures string "measures:beats:divisions" ("m:b⇔:d").

Public Member Functions

• midi measures ()

Default constructor for midi_measures.

midi_measures (int measures, int beats, int divisions)

Principal constructor for midi_measures.

• int measures () const

'Getter' function for member m_measures

void measures (int m)

'Setter' function for member m_measures

• int beats () const

'Getter' function for member m_beats

void beats (int b)

 ${\it 'Setter' function for member m_beats}$

• int divisions () const

'Getter' function for member m divisions

void divisions (int d)

'Setter' function for member m_divisions

Private Attributes

• int m_measures

The integral number of measures in the measures-based time.

• int m_beats

The integral number of beats in the measures-based time.

• int m_divisions

The integral number of divisions/pulses in the measures-based time.

12.39.1 Detailed Description

More commonly known as "bars:beats:ticks", or "BBT".

12.39.2 Constructor & Destructor Documentation

```
12.39.2.1 seq64::midi_measures::midi_measures()
```

12.39.2.2 seq64::midi_measures::midi_measures (int measures, int beats, int divisions)

Parameters

measures	Copied into the m_measures member.
beats	Copied into the m_beats member.
divisions	Copied into the m_divisions member.

12.39.3 Member Function Documentation

```
12.39.3.1 int seq64::midi_measures::measures() const [inline]
```

```
12.39.3.2 void seq64::midi_measures::measures ( int m ) [inline]
```

Parameters

```
m The value to which to set the number of measures. We can add validation later.
```

```
12.39.3.3 int seq64::midi_measures::beats ( ) const [inline]
```

12.39.3.4 void seq64::midi_measures::beats (int b) [inline]

Parameters

b The value to which to set the number of beats. We can add validation later.

12.39.3.5 int seq64::midi_measures::divisions () const [inline]

12.39.3.6 void seq64::midi_measures::divisions (int d) [inline]

Parameters

d The value to which to set the number of divisions. We can add validation later.

12.39.4 Field Documentation

```
12.39.4.1 int seq64::midi_measures::m_measures [private]
12.39.4.2 int seq64::midi_measures::m_beats [private]
12.39.4.3 int seq64::midi_measures::m_divisions [private]
```

There are two possible translations of the two bytes of a division. If the top bit of the 16 bits is 0, then the time division is in "ticks per beat" (or "pulses per quarter note"). If the top bit is 1, then the time division is in "frames per second". This member deals only with the ticks/beat definition.

12.40 seq64::midi_splitter Class Reference

This class handles the parsing and writing of MIDI files.

Public Member Functions

midi_splitter (int ppqn=SEQ64_USE_DEFAULT_PPQN)

Principal constructor.

• \sim midi_splitter ()

A rote destructor.

bool log_main_sequence (sequence &seq, int seqnum)

Logs the main sequence (an SMF 0 track) for later usage in splitting the track.

· void initialize ()

Resets the SMF 0 support variables in preparation for parsing a new MIDI file.

• void increment (int channel)

Processes a channel number by raising its flag in the m_smf0_channels[] array.

bool split (perform &p, int screenset)

This function splits an SMF 0, splitting all of the channels in the sequence out into separate sequences, and adding each to the perform object.

int ppqn () const

'Getter' function for member m_ppqn Provides a way to get the actual value of PPQN used in processing the sequences when parse() was called.

· int count () const

'Getter' function for member m_smf0_channels_count

Private Member Functions

bool split_channel (const sequence &main_seq, sequence *seq, int channel)

This function splits the given sequence into new sequences, one for each channel found in the SMF 0 track.

Private Attributes

• int m_ppqn

Provides the current value of the PPQN, which used to be constant and is now only the macro DEFAULT PPQN.

· bool m_use_default_ppqn

Indicates that the default PPQN is in force.

int m_smf0_channels_count

Provides support for SMF 0, indicates how many channels were found in the file in a single sequence.

bool m smf0 channels [16]

Provides support for SMF 0, holds a bool value that indicates the occurrence of a given channel.

• sequence * m_smf0_main_sequence

Provides support for SMF 0, points to the initial SMF 0 sequence, from which the single-channel sequences will be created.

int m_smf0_seq_number

Provides support for SMF 0, holds the prospective sequence number of the main (SMF 0) sequence.

12.40.1 Detailed Description

In addition to the standard MIDI tracks, it also handles some "private" or "proprietary" tracks specific to Seq24. It does not, however, handle SYSEX events.

12.40.2 Constructor & Destructor Documentation

12.40.2.1 seq64::midi_splitter::midi_splitter(int ppqn = SEQ64_USE_DEFAULT_PPQN)

Parameters

ppqn

Provides the initial value of the PPQN setting. It is handled differently for parsing (reading) versus writing the MIDI file.

- · Reading.
 - If set to SEQ64_USE_DEFAULT_PPQN, the legacy application behavior is used. The
 m_ppqn member is set to the default PPQN, DEFAULT_PPQN. The value read from the
 MIDI file, ppqn, is then use to scale the running-time of the sequence relative to
 DEFAULT_PPQN.
 - Otherwise, m_ppqn is set to the value read from the MIDI file. No scaling is done. Since the value gets written, specify ppqn as 0, an obviously bogus value, to get this behavior.
- Writing. This value is written to the MIDI file in the header chunk of the song. Note that the caller
 must query for the PPQN set during parsing, and pass it to the constructor when preparing to
 write the file. See how it is done in the mainwand class.

12.40.2.2 seq64::midi_splitter::~midi_splitter()

12.40.3 Member Function Documentation

12.40.3.1 bool seg64::midi_splitter::log_main_sequence (_sequence & seq, int segnum_)

/param seq The main sequence to be logged.

/param segnum The sequence number of the main sequence.

/return Returns true if the main sequence's address was logged, and false if it was already logged.

```
12.40.3.2 void seq64::midi_splitter::initialize ( )
```

```
12.40.3.3 void seq64::midi_splitter::increment ( int channel )
```

If it is the first entry for that channel, m_smf0_channels_count is incremented. We won't check the channel number, to save time, until someday we segfault :-D

Parameters

channel	The MIDI channel number. The caller is responsible to make sure it ranges from 0 to 15.
---------	---

```
12.40.3.4 bool seq64::midi_splitter::split ( perform & p, int screenset )
```

Lastly, it adds the SMF 0 track as the last track; the user can then examine it before removing it. Is this worth the effort?

There is a little oddity, in that, if the SMF 0 track has events for only one channel, this code will still create a new sequence, as well as the main sequence. Not sure if this is worth extra code to just change the channels on the main sequence and put it into the correct track for the one channel it contains. In fact, we just want to keep it in patter slot number 16, to keep it out of the way.

Parameters

р	Provides a reference to the perform object into which sequences/tracks are to be added.
screenset	The screen-set offset to be used when loading a sequence (track) from the file.

Returns

Returns true if the parsing succeeded. Returns false if no SMF 0 main sequence was logged.

```
12.40.3.5 int seq64::midi_splitter::ppqn( ) const [inline]
```

The PPQN will be either the global ppqn (legacy behavior) or the value read from the file, depending on the ppqn parameter passed to the midi_splitter constructor.

```
12.40.3.6 int seq64::midi_splitter::count( ) const [inline]
```

```
12.40.3.7 bool seq64::midi_splitter::split_channel ( const sequence & main_seq, sequence * s, int channel )

[private]
```

Note that the events that are read from the MIDI file have delta times. Sequencer64 converts these delta times to cumulative times. We need to preserve that here. Conversion back to delta times is needed only when saving the sequences to a file. This is done in midi_container::fill().

We have to accumulate the delta times in order to be able to set the length of the sequence in pulses.

Luckily, we don't have to worry about copying triggers, since the imported SMF 0 track won't have any Seq24/← Sequencer24 triggers.

It doesn't set the sequence number of the sequence; that is set when the sequence is added to the perform object.

Parameters

main_seq	This parameter is the whole SMF 0 track that was read from the MIDI file. It contains all of the channel data that needs to be split into separate sequences.
s	Provides the new sequence that needs to have its settings made, and all of the selected channel events added to it.
channel	Provides the MIDI channel number (re 0) that marks the channel data the needs to be extracted and added to the new sequence.

Returns

Returns true if at least one event got added. If none were added, the caller should delete the sequence object represented by parameter *s*.

12.40.4 Field Documentation

```
12.40.4.1 int seq64::midi_splitter::m_ppqn [private]
```

12.40.4.2 bool seq64::midi_splitter::m_use_default_ppqn [private]

12.40.4.3 int seq64::midi_splitter::m_smf0_channels_count [private]

SMF 1 file parsing will only warn about more than one channel found in a given sequence.

```
12.40.4.4 bool seq64::midi_splitter::m_smf0_channels[16] [private]
```

Obviously, we don't have to worry about multiple MIDI busses.

```
12.40.4.5 sequence* seq64::midi_splitter::m_smf0_main_sequence [private]
```

```
12.40.4.6 int seq64::midi_splitter::m_smf0_seq_number [private]
```

We want to be able to add that sequence last, for easier and cleaner removal of that sequence by the user.

12.41 seq64::midi_timing Class Reference

We anticipate the need to have a small structure holding the parameters needed to calculate MIDI times within an arbitrary song.

Public Member Functions

• midi_timing ()

Defaults constructor for midi_timing.

midi_timing (int bpminute, int bpmeasure, int beatwidth, int ppqn)

Principal constructor for midi_timing.

• int beats_per_minute () const

'Getter' function for member m_beats_per_minute

void beats_per_minute (int b)

'Setter' function for member m_beats_per_minute

• int beats_per_measure () const

'Getter' function for member m_beats_per_measure

• void beats_per_measure (int b)

'Setter' function for member m_beats_per_measure

• int beat_width () const

'Getter' function for member m_beats_per_beat_width

void beat_width (int bw)

'Setter' function for member m_beats_per_beat_width

• int ppqn () const

'Getter' function for member m_ppqn

• void ppqn (int p)

'Setter' function for member m_ppqn

Private Attributes

• int m beats per minute

This value should match the BPM value selected when editing the song.

• int m_beats_per_measure

This value should match the numerator value selected when editing the sequence.

int m_beat_width

This value should match the denominator value selected when editing the sequence.

• int m_ppqn

This value provides the precision of the MIDI song.

12.41.1 Detailed Description

Although Seq24/Sequencer64 currently are heavily dependent on hard-wired values, that will be rectified eventually, so let us get ready for it.

12.41.2 Constructor & Destructor Documentation

```
12.41.2.1 seq64::midi_timing::midi_timing()
```

12.41.2.2 seq64::midi_timing::midi_timing (int bpminute, int bpmeasure, int beatwidth, int ppqn)

bpminute	Copied into the m_beats_per_minute member.
bpmeasure	Copied into the m_beats_per_measure member.
beatwidth	Copied into the m_beat_width member.
ppqn	Copied into the m_ppqn member.

12.41.3 Member Function Documentation

```
12.41.3.1 int seq64::midi_timing::beats_per_minute( ) const [inline]
```

```
12.41.3.2 void seq64::midi_timing::beats_per_minute( int b ) [inline]
```

Parameters

b The value to which to set the number of beats/minute. We can add validation later.

```
12.41.3.3 int seq64::midi_timing::beats_per_measure( ) const [inline]
```

```
12.41.3.4 void seq64::midi_timing::beats_per_measure(int b) [inline]
```

Parameters

b The value to which to set the number of beats/measure. We can add validation later.

```
12.41.3.5 int seq64::midi_timing::beat_width() const [inline]
```

12.41.3.6 void seq64::midi_timing::beat_width(int bw) [inline]

Parameters

bw The value to which to set the number of beats in the denominator of the time signature. We can add validation later.

```
12.41.3.7 int seq64::midi_timing::ppqn() const [inline]
```

12.41.3.8 void seq64::midi_timing::ppqn(int p) [inline]

Parameters

p The value to which to set the PPQN member. We can add validation later.

12.41.4 Field Documentation

12.41.4.1 int seq64::midi_timing::m_beats_per_minute [private]

This value is most commonly set to 120, but is also read from the MIDI file. This value is needed if one want to calculate durations in true time units such as seconds, but is not needed to calculate the number of pulses/ticks/divisions.

12.41.4.2 int seq64::midi_timing::m_beats_per_measure [private]

This value is most commonly set to 4.

12.41.4.3 int seq64::midi_timing::m_beat_width [private]

This value is most commonly set to 4, meaning that the fundamental beat unit is the quarter note.


12.41.4.4 int seq64::midi_timing::m_ppqn [private]

This value is most commonly set to 192, but is also read from the MIDI file. We are still working getting "non-standard" values to work.

12.42 seq64::midi_vector Class Reference

This class is the std::vector implementation of the midi_container.

Inheritance diagram for seq64::midi_vector:



Public Member Functions

• midi_vector (sequence &seq)

This constructor fills in the members of this class.

virtual ∼midi_vector ()

A rote constructor needed for a base class.

• virtual std::size_t size () const

• virtual bool done () const

For iterating through the data in the MIDI vector, we are done when we've gotten the last element of the container.

virtual void put (midibyte b)

Provides a way to add a MIDI byte into the list.

virtual midibyte get () const

Provide a way to get the next byte from the container.

· virtual void clear ()

Provides a way to clear the container.

Private Types

typedef std::vector< midibyte > CharVector

Provides the type of this container.

Private Attributes

· CharVector m char vector

The container itself.

Additional Inherited Members

12.42.1 Member Typedef Documentation

```
12.42.1.1 typedef std::vector<midibyte> seq64::midi_vector::CharVector [private]
```

12.42.2 Constructor & Destructor Documentation

```
12.42.2.1 seq64::midi_vector::midi_vector ( sequence & seq )
```

Parameters

seq Provides a reference to the sequence/track for which this container holds MIDI data.

```
12.42.2.2 virtual seq64::midi_vector::~midi_vector() [inline], [virtual]
```

12.42.3 Member Function Documentation

```
12.42.3.1 virtual std::size_t seq64::midi_vector::size( ) const [inline], [virtual]
```

Returns

Returns the size of the container, in midibytes.

Reimplemented from seq64::midi_container.

```
12.42.3.2 virtual bool seq64::midi_vector::done() const [inline], [virtual]
```

Returns

Returns true if the position is greater than or equal to the size of the character vector.

Reimplemented from seg64::midi container.

```
12.42.3.3 virtual void seq64::midi_vector::put( midibyte b ) [inline], [virtual]
```

The original seq24 list used an std::list and a push_front operation.

Parameters

```
b Provides the MIDI byte to push_back() into the character vector.
```

Implements seq64::midi container.

```
12.42.3.4 virtual midibyte seq64::midi_vector::get( ) const [inline], [virtual]
```

In this implementation, m_position_for_get is used. As a side-effect, the position value is incremented.

Returns

Returns the next byte in the character vector.

Implements seq64::midi_container.

```
12.42.3.5 virtual void seq64::midi_vector::clear() [inline], [virtual]
```

Implements seq64::midi_container.

12.42.4 Field Documentation

12.42.4.1 CharVector seq64::midi_vector::m_char_vector [private]

12.43 seq64::midibus Class Reference

Provides a class for handling the MIDI buss on Linux.

Public Member Functions

 midibus (int localclient, int destclient, int destport, snd_seq_t *seq, const char *client_name, const char *port name, int id, int queue, int ppqn=SEQ64 USE DEFAULT PPQN)

Provides a constructor with client number, port number, ALSA sequencer support, name of client, name of port.

• midibus (int localclient, snd_seq_t *seq, int id, int queue, int ppqn=SEQ64_USE_DEFAULT_PPQN)

Secondary constructor.

• ∼midibus ()

A rote empty destructor.

• bool init_out ()

Initialize the MIDI output port.

• bool init_in ()

Initialize the MIDI input port.

• bool deinit in ()

Deinitialize the MIDI input.

• bool init out sub ()

Initialize the output in a different way?

bool init_in_sub ()

Initialize the output in a different way?

void print ()

Prints m_name.

const std::string & get_name () const

'Getter' function for member n_name

· int get id () const

'Getter' function for member m_id

void play (event *e24, midibyte channel)

This play() function takes a native event, encodes it to an ALSA event, and puts it in the queue.

void sysex (event *e24)

Takes a native SYSEX event, encodes it to an ALSA event, and then puts it in the queue.

void start ()

This function gets the MIDI clock a-runnin', if the clock type is not e_clock_off.

• void stop ()

Stop the MIDI buss.

void clock (midipulse tick)

Generates the MIDI clock, starting at the given tick value.

void continue_from (midipulse tick)

Continue from the given tick.

· void init_clock (midipulse tick)

Initialize the clock, continuing from the given tick.

void set_clock (clock_e clocktype)

'Setter' function for member m_clock_type

clock_e get_clock () const

'Getter' function for member m_clock_type

void set_input (bool inputing)

Set status to of "inputting" to the given value.

bool get_input () const

'Getter' function for member m_inputing

· void flush ()

Flushes our local queue events out into ALSA.

• int get client () const

'Getter' function for member m_dest_addr_client The address of client.

• int get_port () const

'Getter' function for member m_dest_addr_port

Static Public Member Functions

static void set clock mod (int clockmod)

Set the clock mod to the given value, if legal.

static int get_clock_mod ()

Get the clock mod value.

Private Attributes

• int m id

The ID of the midibus object.

clock_e m_clock_type

The type of clock to use.

· bool m inputing

TRD

int m_ppqn

Provides the PPQN value in force, currently a constant.

• snd seq t *const m seq

ALSA sequencer client handle.

· const int m_dest_addr_client

Destination address of client.

· const int m dest addr port

Destination port of client.

const int m_local_addr_client

Local address of client.

• int m_local_addr_port

Local port of client.

• int m_queue

Another ID of the MIDI queue?

• std::string m_name

The name of the MIDI buss.

• midipulse m_lasttick

The last (most recent? final?) tick.

• mutex m_mutex

Locking mutex.

Static Private Attributes

• static int m_clock_mod

This is another name for "16 * 4".

Friends

· class mastermidibus

The master MIDI bus sets up the buss.

12.43.1 Constructor & Destructor Documentation

12.43.1.1 seq64::midibus::midibus (int *localclient*, int *destclient*, int *destport*, snd_seq_t * seq, const char * client_name, const char * port_name, int id, int queue, int ppqn = SEQ64_USE_DEFAULT_PPQN)

localclient	Provides the local-client number.
destclient	Provides the destination-client number.
destport	Provides the destination-client port.
seq	Provides the sequence that will work with this buss.
client_name	Provides the client name, but this parameter is unused.
port_name	Provides the port name.
id	Provides the ID code for this bus. It is an index into the midibus definitions array, and is also used in the constructed human-readable buss name.
queue	Provides the queue ID.
ppqn	Provides the PPQN value.

12.43.1.2 seq64::midibus::midibus (int localclient, snd_seq_t * seq, int id, int queue, int ppqn = SEQ64_USE_DEFAULT_PPQN)

Similar to the principal constructor, but labels the buss by number more than by name.

Parameters

localclient	Provides the local-client number.
seq	Provides the sequence that will work with this buss.
id	Provides the ID code for this bus. It is an index into the midibus definitions array, and is also used
	in the constructed human-readable buss name.
queue	Provides the queue ID.
ppqn	Provides the PPQN value.

12.43.1.3 seq64::midibus:: \sim midibus ()

12.43.2 Member Function Documentation

12.43.2.1 bool seq64::midibus::init_out()

Returns

Returns true unless setting up ALSA MIDI failed in some way.

12.43.2.2 bool seq64::midibus::init_in()

Returns

Returns true unless setting up ALSA MIDI failed in some way.

12.43.2.3 bool seq64::midibus::deinit_in()

Set the input and the output ports. The destination port is actually our local port.

Returns

Returns true, unless an error occurs.

```
12.43.2.4 bool seq64::midibus::init_out_sub()
```

Returns

Returns true unless setting up the ALSA port failed in some way.

```
12.43.2.5 bool seq64::midibus::init_in_sub()
```

Returns

Returns true unless setting up the ALSA port failed in some way.

```
12.43.2.6 void seq64::midibus::print()

12.43.2.7 const std::string& seq64::midibus::get_name() const [inline]

12.43.2.8 int seq64::midibus::get_id() const [inline]
```

12.43.2.9 void seq64::midibus::play (event * e24, midibyte channel)

Threadsafe

Parameters

e24	The event to be played on this bus.
channel	The channel of the playback.

12.43.2.10 void seq64::midibus::sysex (event * e24)

Parameters

e24	The event to be handled.

```
12.43.2.11 void seq64::midibus::start ( )
```

12.43.2.12 void seq64::midibus::stop()

12.43.2.13 void seq64::midibus::clock (midipulse tick)

Parameters

tick	Provides the starting tick.
------	-----------------------------

12.43.2.14 void seq64::midibus::continue_from (midipulse tick)

tick	The continuing tick.
------	----------------------

12.43.2.15 void seq64::midibus::init_clock (midipulse tick)

Parameters

tick	The starting tick.
------	--------------------

12.43.2.16 void seq64::midibus::set_clock (clock e clocktype) [inline]

Parameters

clocktype	The value used to set the clock-type.
CIOCKLYPC	The value asea to set the clock type.

12.43.2.17 clock_e seq64::midibus::get_clock() const [inline]

12.43.2.18 void seq64::midibus::set_input (bool inputing)

If the parameter is true, then init_in() is called; otherwise, deinit_in() is called.

Parameters

innutina	The inputing value to cet
IIIPutilig	The inputing value to set.

```
12.43.2.19 bool seq64::midibus::get_input( ) const [inline]
```

12.43.2.20 void seq64::midibus::flush ()

12.43.2.21 int seq64::midibus::get_client() const [inline]

12.43.2.22 int seq64::midibus::get_port() const [inline]

12.43.2.23 static void seq64::midibus::set_clock_mod (int clockmod) [inline], [static]

Parameters

clockmod If this value is not equal to 0, it is used to set the static member m_clock_mod.

12.43.2.24 static int seq64::midibus::get_clock_mod() [inline], [static]

12.43.3 Friends And Related Function Documentation

```
12.43.3.1 friend class mastermidibus [friend]
12.43.4 Field Documentation
12.43.4.1 int seq64::midibus::m_clock_mod [static], [private]
Initialize this static member.
12.43.4.2 int seq64::midibus::m_id [private]
12.43.4.3 clock_e seq64::midibus::m_clock_type [private]
12.43.4.4 bool seq64::midibus::m_inputing [private]
12.43.4.5 int seq64::midibus::m_ppqn [private]
12.43.4.6 snd_seq_t* const seq64::midibus::m_seq [private]
12.43.4.7 const int seq64::midibus::m_dest_addr_client [private]
12.43.4.8 const int seq64::midibus::m_dest_addr_port [private]
12.43.4.9 const int seq64::midibus::m_local_addr_client [private]
12.43.4.10 int seq64::midibus::m_local_addr_port [private]
12.43.4.11 int seq64::midibus::m_queue [private]
12.43.4.12 std::string seq64::midibus::m_name [private]
12.43.4.13 midipulse seq64::midibus::m_lasttick [private]
12.43.4.14 mutex seq64::midibus::m_mutex [private]
```

12.44 seq64::midifile Class Reference

This class handles the parsing and writing of MIDI files.

Public Member Functions

 midifile (const std::string &name, int ppqn=SEQ64_USE_DEFAULT_PPQN, bool oldformat=false, bool globalbgs=true)

Principal constructor.

∼midifile ()

A rote destructor.

bool parse (perform &p, int a_screen_set=0)

This function opens a binary MIDI file and parses it into sequences and other application objects.

• bool write (perform &p)

Write the whole MIDI data and Seg24 information out to the file.

- bool write song (perform &p)
- const std::string & error_message () const

'Getter' function for member m_error_message

bool error_is_fatal () const

'Getter' function for member m_error_is_fatal

• int ppqn () const

'Getter' function for member m_ppqn Provides a way to get the actual value of PPQN used in processing the sequences when parse() was called.

Private Member Functions

bool parse_smf_0 (perform &p, int screenset)

This function parses an SMF 0 binary MIDI file as if it were an SMF 1 file, then, if more than one MIDI channel was encountered in the sequence, splits all of the channels in the sequence out into separate sequences.

bool parse_smf_1 (perform &p, int screenset, bool is_smf0=false)

This function parses an SMF 1 binary MIDI file; it is basically the original seq24 midifile::parse() function.

midilong parse_prop_header (int file_size)

Parse the proprietary header, figuring out if it is the new format, or the legacy format, for sequencer-specific data.

· bool parse proprietary track (perform &a perf, int file size)

After all of the conventional MIDI tracks are read, we're now at the "proprietary" Seq24 data section, which describes the various features that Seq24 supports.

• int pow2 (int logbase2)

Internal function for simple calculation of a power of 2 without a lot of math.

bool checklen (midilong len, midibyte type)

Internal function to check for and report a bad length value.

void add_trigger (sequence &seq, midishort ppqn)

Internal function to make the parser easier to read.

midilong read long ()

Reads 4 bytes of data using read_byte().

midishort read_short ()

Reads 2 bytes of data using read_byte().

midibyte read_byte ()

Reads 1 byte of data directly from the m_data vector, incrementing m_pos after doing so.

midilong read_varinum ()

Read a MIDI Variable-Length Value (VLV), which has a variable number of bytes.

• void write long (midilong value)

Writes 4 bytes, each extracted from the long value and shifted rightward down to byte size, using the write_byte() function.

void write_short (midishort value)

Writes 2 bytes, each extracted from the long value and shifted rightward down to byte size, using the write_byte() function.

• void read_byte_array (midibyte *b, int len)

A helper function to simplify reading midi_control data from the MIDI file.

• void write byte (midibyte c)

Writes 1 byte.

· void write varinum (midilong)

Writes a MIDI Variable-Length Value (VLV), which has a variable number of bytes.

void write_track_name (const std::string &trackname)

Writes out a track name.

std::string read_track_name ()

Reads the track name.

• void write seq number (midishort seqnum)

Writes out a sequence number.

• int read_seq_number ()

Reads the sequence number.

void write track end ()

Writes out the end-of-track marker.

· bool write header (int numtracks)

We want to write:

• void write_prop_header (midilong tag, long len)

Writes a "proprietary" (SeqSpec) Seq24 footer header in either the new MIDI-compliant format, or the legacy Seq24 format.

bool write_proprietary_track (perform &a_perf)

Writes out the final proprietary/SeqSpec section, using the new format if the legacy format is not in force.

· long varinum_size (long len) const

Calculates the length of a variable length value.

long prop_item_size (long datalen) const

Calculates the size of a proprietary item, as written by the write_prop_header() function, plus whatever is called to write the data.

• long track_name_size (const std::string &trackname) const

Calculates the size of a trackname and the meta event that specifies it.

void errdump (const std::string &msg)

Helper function to emit more useful error messages.

void errdump (const std::string &msg, unsigned long p)

Helper function to emit more useful error messages for erroneous long values.

- void write_track (const midi_vector &lst)
- long seq_number_size () const

Returns the size of a sequence-number event, which is always 5 bytes, plus one byte for the delta time that precedes it.

· long track end size () const

Returns the size of a track-end event, which is always 3 bytes.

• bool is_sysex_special_id (midibyte ch)

Check for special SysEx ID byte.

Private Attributes

• mutex m_mutex

Provides locking for the sequence.

• int m_file_size

Holds the size of the MIDI file.

std::string m_error_message

Holds the last error message, useful for trouble-shooting without having Sequencer64 running in a console window.

bool m_error_is_fatal

Indicates if the error should be considered fatal.

· bool m_disable_reported

Indicates that file reading has already been disabled (due to serious errors), so don't complain about it anymore.

int m_pos

Holds the position in the MIDI file.

• const std::string m name

The unchanging name of the MIDI file.

std::vector< midibyte > m_data

This vector of characters holds our MIDI data.

std::list< midibyte > m char list

Provides a list of characters.

bool m_new_format

Use the new format for the proprietary footer section of the Seq24 MIDI file.

• bool m_global_bgsequence

Indicates to store the new key, scale, and background sequence in the global, "proprietary" section of the MIDI song.

• int m_ppqn

Provides the current value of the PPQN, which used to be constant and is now only the macro DEFAULT_PPQN.

· bool m use default ppqn

Indicates that the default PPQN is in force.

midi_splitter m_smf0_splitter

Provides support for SMF 0.

12.44.1 Detailed Description

In addition to the standard MIDI tracks, it also handles some "private" or "proprietary" tracks specific to Seq24. It does not, however, handle SYSEX events.

12.44.2 Constructor & Destructor Documentation

12.44.2.1 seq64::midifile::midifile (const std::string & name, int ppqn = SEQ64_USE_DEFAULT_PPQN, bool oldformat = false, bool globalbgs = true)

Parameters

name Provides the name of the MIDI file to be read or written.

Parameters

ppqn	Provides the initial value of the PPQN setting. It is handled differently for parsing (reading) versus writing the MIDI file.
	Reading.
	 If set to SEQ64_USE_DEFAULT_PPQN, the legacy application behavior is used. The m_ppqn member is set to the default PPQN, DEFAULT_PPQN. The value read from the MIDI file, ppqn, is then use to scale the running-time of the sequence relative to DEFAULT_PPQN.
	 Otherwise, m_ppqn is set to the value read from the MIDI file. No scaling is done. Since the value gets written, specify ppqn as 0, an obviously bogus value, to get this behavior.
	 Writing. This value is written to the MIDI file in the header chunk of the song. Note that the caller must query for the PPQN set during parsing, and pass it to the constructor when preparing to write the file. See how it is done in the mainwand class.
oldformat	If true, write out the MIDI file using the old Seq24 format, instead of the new MIDI-compliant sequencer-specific format, for the seq24-specific SeqSpec tags defined in the globals module. This option is false by default. Note that this option is only used in writing; reading can handle either format transparently.
globalbgs	If true, write any non-default values of the key, scale, and background sequence to the global "proprietary" section of the MIDI file, instead of to each sequence. Note that this option is only used in writing; reading can handle either format transparently.

12.44.2.2 seq64::midifile::~midifile()

12.44.3 Member Function Documentation

12.44.3.1 bool seq64::midifile::parse (perform & p, int screenset = 0)

In addition to the standard MIDI track data in a normal track, Seq24/Sequencer64 adds four sequencer-specific events just before the end of the track:

```
c_triggers_new:
                       SeqSpec FF 7F 1C 24 24 00 08 00 00 ...
    c_midibus:
                       SeqSpec FF 7F 05 24 24 00 01 00
                       SeqSpec FF 7F 06 24 24 00 06 04 04
    c_timesig:
    c_midich:
                       SeqSpec FF 7F 05 24 24 00 02 06
Note that only Sequencer64 adds "FF 7F len" to the SeqSpec data.
Standard MIDI provides for port and channel specification meta events, but
they are apparently considered obsolete:
    Obsolete meta-event:
                                       Replacement:
    MIDI port (buss): FF 21 01 po
                                      Device (port) name: FF 09 len text
    MIDI channel:
                      FF 20 01 ch
What do other applications use for specifying port/channel?
```

Note the is-modified flag: We now assume that the perform object is starting from scratch when parsing. But we let mainwnd tell the perform object when to clear everything with perform::clear_all(). The mainwnd does this for a new file, opening a file, but not for a file import, which might be done simply to add more MIDI tracks to the current composition. So, if parsing succeeds, all we want to do is make sure the flag is set. Parsing a file successfully is not always a modification of the setup. For instance, the first read of a MIDI file should start clean, not dirty.

SysEx notes:

Some files (e.g. Dixie04.mid) do not always encode System Exclusive messages properly for a MIDI file. Instead of a varinum length value, they are followed by extended IDs (0x7D, 0x7E, or 0x7F).

We've covered some of those cases by disabling access to m_data if the position passes the size of the file, but we want try to bypass these odd cases properly. So we look ahead for one of these special values.

Currently, Sequencer64, like Se24, handles SysEx message only to the extend of passing them via MIDI Thru. We hope to improve on that capability.

Parameters

р	Provides a reference to the perform object into which sequences/tracks are to be added.
screenset	The screen-set offset to be used when loading a sequence (track) from the file. This value ranges from -31 to 0 to +31 (32 is the maximum screen-set available in Seq24). This offset is added to the sequence number read in for the sequence, to place it elsewhere in the imported tune, and locate it in a specific screen-set. If this parameter is non-zero, then we will assume that the perform data is dirty.
	io dirty.

Returns

Returns true if the parsing succeeded. Note that the error status is saved in m_error_is_fatal, and a message (to display later) is saved in m_error_message.

12.44.3.2 bool seq64::midifile::write (perform & p)

Also see the write_song() function, for exporting to standard MIDI.

Seq24 reverses the order of some events, due to popping from its container. Not an issue here.

Parameters

p Provides the object that will contain and manage the entire performance.

Returns

Returns true if the write operations succeeded.

```
12.44.3.3 bool seq64::midifile::write_song ( perform & p )
12.44.3.4 const std::string& seq64::midifile::error_message ( ) const [inline]
12.44.3.5 bool seq64::midifile::error_is_fatal( ) const [inline]
12.44.3.6 int seq64::midifile::ppqn( ) const [inline]
```

The PPQN will be either the global ppqn (legacy behavior) or the value read from the file, depending on the ppqn parameter passed to the midifile constructor.

12.44.3.7 bool seq64::midifile::parse_smf_0 (perform & p, int screenset) [private]

The original sequence remains in place, in sequence slot 16 (the 17th slot). The user is responsible for deleting it if it is not needed.

Parameters

р	Provides a reference to the perform object into which sequences/tracks are to be added.
screenset	The screen-set offset to be used when loading a sequence (track) from the file.

Returns

Returns true if the parsing succeeded.

12.44.3.8 bool seq64::midifile::parse_smf_1 (perform & p, int screenset, bool is_smf0 = false) [private]

It assumes the file-data has already been read into memory. It also assumes that the ID, track-length, and format have already been read.

If the MIDI file contains both proprietary (c_timesig) and MIDI type 0x58 then it came from seq42 or seq32 (Stazed versions). In this case the MIDI type is parsed first (because it is listed first) then it gets overwritten by the proprietary, above.

Parameters

р	Provides a reference to the perform object into which sequences/tracks are to be added.
screenset	The screen-set offset to be used when loading a sequence (track) from the file.
is_smf0	True if we detected that the MIDI file is in SMF 0 format.

Returns

Returns true if the parsing succeeded.

12.44.3.9 midilong seq64::midifile::parse_prop_header(int file_size) [private]

The new format creates a final track chunk, starting with "MTrk". Then comes the delta-time (here, 0), and the event. An event is a MIDI event, a SysEx event, or a Meta event.

A MIDI Sequencer Specific meta message includes either a delta time or absolute time, and the MIDI Sequencer Specific event encoded as follows:

0x00 0xFF 0x7F length data

For convenience, this function first checks the amount of file data left. If enough, then it reads a long value. If the value starts with 0×00 0xFF 0x7F, then that is a SeqSpec event, which signals usage of the new Sequencer64 "proprietary" format. Otherwise, it is probably the old format, and the long value is a control tag $(0 \times 242400 \text{nn})$, which can be returned immedidately.

If it is the new format, we back up to the FF, then get the next byte, which should be a 7F. If so, then we read the length (a variable length value) of the data, and then read the long value, which should be the control tag, which, again, is returned by this function.

Note

Most sequencers seem to be tolerant of both the lack of an "MTrk" marker and of the presence of an unwrapped control tag, and so can handle both the old and new formats of the final proprietary track.

Parameters

file_size	The size of the data file. This value is compared against the member m_pos (the position inside
	m_data[]), to make sure there is enough data left to process.

Returns

Returns the control-tag value found. These are the values, such as c_midich, found in the globals module, that indicate the type of sequencer-specific data that comes next. If there is not enough data to process, then 0 is returned.

12.44.3.10 bool seq64::midifile::parse_proprietary_track(perform & p, int file_size) [private]

It consists of series of tags:

```
c_midictrl
c_midiclocks
c_notes
c_bpmtag (beats per minute)
c_mutegroups
c_musickey (new, added if usr() global_seq_feature() is true)
c_musicscale (ditto)
c_backsequence (ditto)
```

(There are more tags defined in the globals module, but they are not used in this function. This doesn't quite make sense, as there are also some "triggers" values, and we're pretty sure the application uses them. Oh, it turns out that they are set up by actions performed on each sequence, and are stored as sequencer-specific ("SeqSpec") data with each track's data as held in the MIDI container for the track. See the midi_container module for more information.)

The format is (1) tag ID; (2) length of data; (3) the data.

First, we separate out this function for a little more clarity. Then we added code to handle reading both the legacy Seq24 format and the new, MIDI-compliant format. Note that even the new format is not quite correct, since it doesn't handle a MIDI manufacturer's ID, making it a single byte that is part of the data. But it does have the "MTrk" marker and track name, so that must be processed for the new format.

Now, in our "midicvt" project, we have a test MIDI file, b4uacuse-non-mtrk.midi that is good, except for having a tag "MUnk" instead of "MTrk". We should consider being more permissive, if possible. Otherwise, though, the only penality is that the "proprietary" chunk is completely skipped.

Parameters

р	The performance object that is being set via the incoming MIDI file.
file_size	The file size as determined in the parse() function.

There are also implicit parameters, with the m_pos and m_new_format member variables.

```
12.44.3.11 int seq64::midifile::pow2 (int logbase2) [private]
```

Use for calculating the denominator of a time signature.

Parameters

logbase2	Provides the power to which 2 is to be raised. This integer is probably only rarely greater than 4
	(which represents a denominator of 16).

Returns

Returns 2 raised to the logbase2 power.

12.44.3.12 bool seq64::midifile::checklen (midilong len, midibyte type) [private]

A length of zero is now considered legal, but a "warning" message is shown. The largest value allowed within a MIDI file is 0x0FFFFFF. This limit is set to allow variable-length quantities to be manipulated as 32-bit integers.

Parameters

len	The length value to be checked, and it should be greater than 0. However, we have seen files with
	zero-length events, such as Lyric events (0x05).
type	The type of meta event. Used for displaying an error.

Returns

Returns true if the length parameter is valid. This now means it is simply less than 0x0FFFFFFF.

12.44.3.13 void seq64::midifile::add_trigger(sequence & seq, midishort ppqn) [private]

Handles only c_triggers_new values, not the old c_triggers value. If m_ppqn isn't set to the default value, then we must scale these triggers accordingly, just as is done for the MIDI events.

Parameters

seq	Provides the sequence to which the trigger is to be added.
ppqn	Provides the ppqn value to use to scale the tick values if m_use_default_ppqn is true. If 0, the ppqn value is not used.

12.44.3.14 midilong seq64::midifile::read_long() [private]

Warning

This code looks endian-dependent and integer-size dependent.

Returns

Returns the four bytes, shifted appropriately and added together, most-significant byte first, to sum to a long value

12.44.3.15 midishort seq64::midifile::read_short() [private]

Returns

Returns the two bytes, shifted appropriately and added together, most-significant byte first, to sum to a short value.

12.44.3.16 midibyte seq64::midifile::read_byte() [private]

Returns

Returns the byte that was read. Returns 0 if there was an error, though there's no way for the caller to determine if this is an error or a good value.

12.44.3.17 midilong seq64::midifile::read_varinum() [private]

This function reads the bytes while bit 7 is set in each byte. Bit 7 is a continuation bit. See write_varinum() for more information.

Returns

Returns the accumulated values as a single number.

12.44.3.18 void seq64::midifile::write_long(midilong x) [private]

Warning

This code looks endian-dependent.

Parameters

x The long value to be written to the MIDI file.

12.44.3.19 void seq64::midifile::write_short(midishort x) [private]

Warning

This code looks endian-dependent.

Parameters

x The short value to be written to the MIDI file.

12.44.3.20 void seq64::midifile::read_byte_array(midibyte * b, int len) [inline], [private]

Parameters

b	The byte array to receive the data.	
len	The number of bytes in the array, and to be read.	

12.44.3.21 void seq64::midifile::write_byte (midibyte *c* **)** [inline], [private]

The byte is written to the m_char_list member, using a call to push_back().

Parameters

c The MIDI byte to be "written".

12.44.3.22 void seq64::midifile::write_varinum(midilong value) [private]

A MIDI file Variable Length Value is stored in bytes. Each byte has two parts: 7 bits of data and 1 continuation bit. The highest-order bit is set to 1 if there is another byte of the number to follow. The highest-order bit is set to 0 if this byte is the last byte in the VLV.

To recreate a number represented by a VLV, first you remove the continuation bit and then concatenate the leftover bits into a single number.

To generate a VLV from a given number, break the number up into 7 bit units and then apply the correct continuation bit to each byte.

In theory, you could have a very long VLV number which was quite large; however, in the standard MIDI file specification, the maximum length of a VLV value is 5 bytes, and the number it represents can not be larger than 4 bytes.

Here are some common cases:

```
Numbers between 0 and 127 (0x7F) are represented by a single byte.
0x80 is represented as "0x81 0x00".
0x0FFFFFFFF (the largest number) is represented as "0xFF 0xFF 0xFF".
```

Also see the varinum_size() function.

Parameters

value	The long value to be encoded as a MIDI varinum, and written to the MIDI file.

12.44.3.23 void seq64::midifile::write_track_name(const std::string & trackname) [private]

Note that we have to precede this "event" with a delta time value, set to 0. The format of the output is "0x00 0xFF 0x03 len track-name-bytes".

Parameters

trackname Provides the name of the track to be written to the

12.44.3.24 std::string seq64::midifile::read_track_name() [private]

Meant only for usage in the proprietary/SeqSpec footer track, in the new file format.

Returns

Returns the track name, or an empty string if there was a problem.

12.44.3.25 void seq64::midifile::write_seq_number(midishort seqnum) [private]

The format is "00 FF 00 02 ss ss", where "02" is actually the constant length of the data. We have to precede these values with a 0 delta time, of course.

Now, for sequence 0, an alternate format is "FF 00 00". But that format can only occur in the first track, and the rest of the tracks then don't need a sequence number, since it is assumed to increment. Our application doesn't bother with that shortcut.

Parameters

seqnum	The sequence number to write.
--------	-------------------------------

12.44.3.26 int seq64::midifile::read_seq_number() [private]

Meant only for usage in the proprietary/SeqSpec footer track, in the new file format.

Returns

Returns the sequence number found, or -1 if it was not found.

```
12.44.3.27 void seq64::midifile::write_track_end( ) [private]
12.44.3.28 bool seq64::midifile::write_header(int numtracks) [private]
```

- 0x4D54726B. The track tag "MTrk". The MIDI spec requires that software can skip over non-standard chunks. "Prop"? Would require a fix to midicvt.
- 0xaabbccdd. The length of the track. This needs to be calculated somehow.
- · 0x00. A zero delta time.
- 0x7f7f. Sequence number, a special value, well out of normal range.
- · The name of the track:
 - "Seg24-Spec"
 - "Sequencer64-S"

Then follows the proprietary/SeqSpec data, written in the normal manner. Finally, tack on the track-end meta-event.

Components of final track size:

```
-# Delta time. 1 byte, always 0x00.

-# Sequence number. 5 bytes. OPTIONAL. We won't write it.

-# Track name. 3 + 10 or 3 + 15

-# Series of proprietary/SeqSpec specs:

-# Prop header:

-# If legacy format, 4 bytes.

-# Otherwise, 2 bytes + varinum_size(length) + 4 bytes.

-# Length of the prop data.

-# Track End. 3 bytes.
```

12.44.3.29 void seq64::midifile::write_prop_header(midilong control_tag, long data_length) [private]

This function does not write the data. It replaces calls such as "write_long(c_midich)" in the proprietary secton of write().

The legacy format just writes the control tag (0x242400xx). The new format writes 0x00 0xFF 0x7F len 0x242400xx; the first 0x00 is the delta time.

In the new format, the 0x24 is a kind of "manufacturer ID". At http://www.midi.org/techspecs/manid. \leftarrow php we see that most manufacturer IDs start with 0x00, and are thus three bytes long, or start with codes at 0x40 and above. Similary, this site shows that no manufacturer uses 0x24:

http://sequence15.blogspot.com/2008/12/midi-manufacturer-ids.html

Warning

Currently, the manufacturer ID is not handled; it is part of the data, which can be misleading in programs that analyze MIDI files.

Parameters

control_tag	Determines the type of sequencer-specific section to be written. It should be one of the value in the globals module, such as c_midibus or c_mutegroups.
data_length	The amount of data that will be written. This parameter does not count the length of the header itself.

```
12.44.3.30 bool seq64::midifile::write_proprietary_track( perform & p ) [private]
```

The first thing to do, for the new format only, is calculate the length of this big section of data. This was quite tricky; we tweaked and adjusted until the midicvt program handled the whole new-format file without emitting any errors.

Here's the basics of what Seq24 did for writing the data in this part of the file:

```
-# Write the c_midictrl value, then write a 0. To us, this looks like
no one wrote any code to write this data. And yet, the parsing
code can handles a non-zero value, which is the number of sequences
as a long value, not a byte. So shouldn't we write 4 bytes, not
one? Yes, indeed, we made a mistake. However, we should be
writing out the full data set as well. But not even Seq24 does
that! Perhaps they decided it was best kept in the "rc"
configuration file.
-# MORE TO COME.
```

-# MORE TO COME

Parameters

p | Provides the object that will contain and manage the entire performance.

Returns

Always returns true. No efficient way to check all of the writes that can happen. Might revisit this issue if some bug crops up.

```
12.44.3.31 long seq64::midifile::varinum_size ( long len ) const [private]
```

This function is needed when calculating the length of a track. Note that it handles only the following situations:

```
https://en.wikipedia.org/wiki/Variable-length_quantity
```

This restriction allows the calculation to be simple and fast.

```
1 byte: 0x00 to 0x7F
2 bytes: 0x80 to 0x3FFF
3 bytes: 0x4000 to 0x001FFFFF
4 bytes: 0x200000 to 0x0FFFFFFF
```

Parameters

len The long value whose length, when encoded as a MIDI varinum, is to be found.

Returns

Returns values as noted above. Anything beyond that range returns 0.

```
12.44.3.32 long seq64::midifile::prop_item_size ( long data_length ) const [private]
```

If using the new format, the length includes the sum of sequencer-specific tag (0xFF 0x7F) and the size of the variable-length value. Then, for legacy and new format, 4 bytes are added for the Seq24 MIDI control value, and

then the data length is added.

Parameters

data_length	Provides the data length value to be encoded.
-------------	---

Returns

Returns the length of the item size, including the delta time, meta bytes, length byes, the control tag, and the data-length itself.

12.44.3.33 long seq64::midifile::track_name_size (const std::string & trackname) const [private]

Parameters

trackname	Provides the name of the track to be written to the MIDI file.
-----------	--

Returns

Returns the length of the event, which is of the format "0x00 0xFF 0x03 len track-name-bytes".

12.44.3.34 void seq64::midifile::errdump(const std::string & msg) [private]

It adds the file offset to the message.

Parameters

msg	The main error message string, without an ending newline character.
-----	---

Returns

The constructed string is returned as a side-effect, in case we want to pass it along to the externally-accessible error-message buffer.

12.44.3.35 void seq64::midifile::errdump (const std::string & msg, unsigned long value) [private]

It adds the file offset to the message.

Parameters

msg	The main error message string, without an ending newline character.
value	The long value to show as part of the message.

Returns

The constructed string is returned as a side-effect, in case we want to pass it along to the externally-accessible error-message buffer.

```
12.44.3.36 void seq64::midifile::write_track( const midi_vector & lst ) [private]
12.44.3.37 long seq64::midifile::seq_number_size() const [inline], [private]
12.44.3.38 long seq64::midifile::track_end_size() const [inline], [private]
12.44.3.39 bool seq64::midifile::is_sysex_special_id(_midibyte ch_) [inline], [private]
Parameters
```

Provides the byte to be checked against 0x7D through 0x7F.

Returns

Returns true if the byte is SysEx special ID.

12.44.4 Field Documentation

```
12.44.4.1 mutex seq64::midifile::m_mutex [mutable], [private]
```

Made mutable for use in certain locked getter functions.

```
12.44.4.2 int seq64::midifile::m_file_size [private]
```

This variable was added when loading a file that caused an attempt to load data well beyond the file-size of the midicvt test file Dixie04.mid.

```
12.44.4.3 std::string seq64::midifile::m_error_message [private]
```

If empty, there's no pending error. Currently most useful in the parse() function.

```
12.44.4.4 bool seq64::midifile::m_error_is_fatal [private]
```

The caller can guery for this value after getting the return value from parse().

```
12.44.4.5 bool seq64::midifile::m_disable_reported [private]
```

Once is enough.

```
12.44.4.6 int seq64::midifile::m_pos [private]
```

This is at least a 31-bit value in the recent architectures running Linux and Windows, so it will handle up to 2 Gb of data. This member is used as the offset into the m_data vector.

```
12.44.4.7 const std::string seq64::midifile::m_name [private]

12.44.4.8 std::vector<midibyte> seq64::midifile::m data [private]
```

We could also use a string of characters, unsigned. This member is resized to the putative size of the MIDI file, in the parse() function. Then the whole file is read into it, as if it were an array. This member is an input buffer.

```
12.44.4.9 std::list<midibyte> seq64::midifile::m_char_list [private]
```

The class pushes each MIDI byte into this list using the write_byte() function. Also note that the write() function calls sequence::fill_list() to fill a temporary std::list<char> (!) buffer, then writes that data backwards to this member. This member is an output buffer.

```
12.44.4.10 bool seq64::midifile::m_new_format [private]
```

In the new format, each sequencer-specfic value (0x242400xx, as defined in the globals module) is preceded by the sequencer-specific prefix, 0xFF 0x7F len id/date). By default, the new format is used, but the user can specify the —legacy (-I) option, or make a soft link to the sequence24 binary called "seq24", to write the data in the old format. [We will eventually add the —legacy option to the "rc" configuration file.] Note that reading can handle either format transparently.

```
12.44.4.11 bool seq64::midifile::m_global_bgsequence [private]

12.44.4.12 int seq64::midifile::m_ppqn [private]

12.44.4.13 bool seq64::midifile::m_use_default_ppqn [private]


12.44.4.14 midi_splitter seq64::midifile::m_smf0_splitter [private]
```

This object holds all of the information needed to split a multi-channel sequence.

12.45 seq64::mutex Class Reference

The mutex class provides a simple wrapper for the pthread_mutex_t type used as a recursive mutex.

Inheritance diagram for seq64::mutex:



Public Member Functions

• mutex ()

The constructor assigns the recursive mutex to the local locking mutex.

· void lock () const

Lock the mutex.

· void unlock () const

Unlock the mutex.

Protected Attributes

• pthread_mutex_t m_mutex_lock

Provides a mutex lock usable by a single module or class.

Static Private Attributes

• static const pthread_mutex_t sm_recursive_mutex

Provides a recursive mutex that can be used by the whole application, and is, apparently.

12.45.1 Constructor & Destructor Documentation

```
12.45.1.1 seq64::mutex::mutex ( )
```

12.45.2 Member Function Documentation

```
12.45.2.1 void seq64::mutex::lock ( ) const
```

12.45.2.2 void seq64::mutex::unlock () const

12.45.3 Field Documentation

```
12.45.3.1 const pthread_mutex_t seq64::mutex::sm_recursive_mutex [static], [private]
```

Define the static recursive mutex and its condition variable.

```
12.45.3.2 pthread_mutex_t seq64::mutex::m_mutex_lock [mutable], [protected]
```

However, this mutex ends up being a copy of the static sm_recursive_mutex (and, of course, a different "object").

12.46 seq64::editable_event::name_value_t Struct Reference

Provides a type that contains the pair of values needed for the various lookup maps that are needed to manage editable events.

Data Fields

· unsigned short event_value

Holds a midibyte value (0x00 to 0xFF) or SEQ64_END_OF_MIDIBYTE_TABLE to indicate the end of an array of name_value_t items.

std::string event_name

Holds the human-readable name for an event code or other numeric value in an array of name_value_t items.

12.46.1 Field Documentation

12.46.1.1 unsigned short seq64::editable_event::name_value_t::event_value

12.46.1.2 std::string seq64::editable_event::name_value_t::event_name

12.47 seq64::options Class Reference

This class supports a full tabbed options dialog.

Inherits Dialog.

Public Member Functions

• options (Gtk::Window &parent, perform &p)

Private Types

Private Member Functions

• perform & perf ()

'Getter' function for member m_mainperf

- void clock_callback_off (int bus, Gtk::RadioButton *button)
- void clock_callback_on (int bus, Gtk::RadioButton *button)
- void clock_callback_mod (int bus, Gtk::RadioButton *button)
- void clock_mod_callback (Gtk::Adjustment *adj)
- void input callback (int bus, Gtk::Button *button)
- void filter_callback (Gtk::Button *button)
- void transport_callback (button type, Gtk::Button *button)
- void mouse_seq24_callback (Gtk::RadioButton *)
- void mouse fruity callback (Gtk::RadioButton *)
- void mouse mod4 callback (Gtk::CheckButton *)
- void mouse_snap_split_callback (Gtk::CheckButton *)
- void lash_support_callback (Gtk::CheckButton *)
- void add_midi_clock_page ()
- void add_midi_input_page ()
- void add_keyboard_page ()
- void add_mouse_page ()
- void add_jack_sync_page ()

Private Attributes

• Gtk::Tooltips * m tooltips

A repository for GTK tooltip support.

perform & m_mainperf

The performance object to which some of these options apply.

• Gtk::Button * m_button_ok

The famous "OK" button's pointer.

• Gtk::CheckButton * m_button_jack_transport

Main JACK transport selection.

• Gtk::CheckButton * m_button_jack_master

Main JACK transport master selection.

Gtk::CheckButton * m_button_jack_master_cond

Main JACK transport master-conditional selection.

• Gtk::Button * m button jack connect

JACK Connect button, which we need to enable/disable for clarity and some additional safety.

• Gtk::Button * m_button_jack_disconnect

JACK Disonnect button, which we need to enable/disable for clarity and some additional safety.

• Gtk::Notebook * m_notebook

Not sure yet what this notebook is for.

12.47.1 Member Enumeration Documentation

```
12.47.1.1 enum seq64::options::button [private]
```

These values are handled in options::transport_callback(). Some of them set JACK-related values in the rc_settings object, while the others set up or tear down the JACK support of sequencer64.

The JACK Transport settings are a little messy. They should be radio buttons, and control each other's settings. Currently, if the user wants to set up for JACK Master, the JACK Transport button must also be checked.

Enumerator

- e_jack_transport Turns on the "with JACK Transport" option, rc_settings::with_jack_transport().
- **e_jack_master** Turns on the "with JACK Master" option, rc_settings::with_jack_master(). If another application is already JACK Master, this will fail.
- e_jack_master_cond Turns on the "with JACK Master" option rc_settings::with_jack_master_cond(). This option makes sequencer64 the JACK Master conditionally, that is, if no other application has claimed that role.
- e_jack_start_mode_live Doesn't directly do anything; the live mode versus song mode is set by the e_← jack start mode song value.
- e_jack_start_mode_song Sets the "JACK start mode" value to true, which means that sequencer64 is in song mode. This value is obtained via rc_settings::song_start_mode(). It will eventually be the start mode that applies to either ALSA or JACK playback.
- e_jack_connect Causes the perform object's JACK initialization function, perform::init_jack(), to be called.
- e_jack_disconnect Causes the perform object's JACK deinitialization function, perform::deinit_jack(), to be called.

12.47.2 Constructor & Destructor Documentation

```
12.47.2.1 seq64::options::options ( Gtk::Window & parent, perform & p )
```

12.47.3 Member Function Documentation

```
12.47.3.1 perform& seq64::options::perf( ) [inline], [private]

12.47.3.2 void seq64::options::clock_callback_off( int bus, Gtk::RadioButton * button ) [private]

12.47.3.3 void seq64::options::clock_callback_on( int bus, Gtk::RadioButton * button ) [private]

12.47.3.4 void seq64::options::clock_callback_mod( int bus, Gtk::RadioButton * button ) [private]

12.47.3.5 void seq64::options::clock_mod_callback( Gtk::Adjustment * adj ) [private]

12.47.3.6 void seq64::options::input_callback( int bus, Gtk::Button * button ) [private]

12.47.3.7 void seq64::options::filter_callback( Gtk::Button * button ) [private]
```

12.47.3.8 void seq64::options::transport_callback(button type, Gtk::Button * button) [private]


```
12.47.3.9 void seq64::options::mouse_seq24_callback( Gtk::RadioButton* ) [private]
12.47.3.10 void seq64::options::mouse_fruity_callback( Gtk::RadioButton* ) [private]
12.47.3.11 void seq64::options::mouse_mod4_callback( Gtk::CheckButton*) [private]
12.47.3.12 void seq64::options::mouse_snap_split_callback( Gtk::CheckButton* ) [private]
12.47.3.13 void seq64::options::lash_support_callback( Gtk::CheckButton * ) [private]
12.47.3.14 void seq64::options::add_midi_clock_page( ) [private]
12.47.3.15 void seq64::options::add_midi_input_page( ) [private]
12.47.3.16 void seq64::options::add_keyboard_page( ) [private]
12.47.3.17 void seq64::options::add_mouse_page( ) [private]
12.47.3.18 void seq64::options::add_jack_sync_page( ) [private]
12.47.4 Field Documentation
12.47.4.1 Gtk::Tooltips* seq64::options::m_tooltips [private]
12.47.4.2 perform& seq64::options::m_mainperf [private]
12.47.4.3 Gtk::Button* seq64::options::m_button_ok [private]
12.47.4.4 Gtk::CheckButton* seq64::options::m_button_jack_transport [private]
12.47.4.5 Gtk::CheckButton* seq64::options::m_button_jack_master [private]
12.47.4.6 Gtk::CheckButton* seq64::options::m_button_jack_master_cond [private]
12.47.4.7 Gtk::Button* seq64::options::m_button_jack_connect [private]
12.47.4.8 Gtk::Button* seq64::options::m_button_jack_disconnect [private]
12.47.4.9 Gtk::Notebook* seq64::options::m_notebook [private]
```

Must be a GTK thang.

12.48 seq64::optionsfile Class Reference

Provides a file for reading and writing the application' main configuration file.

Inheritance diagram for seq64::optionsfile:



Public Member Functions

• optionsfile (const std::string &name)

Principal constructor.

• \sim optionsfile ()

A rote destructor.

• bool parse (perform &perf)

Parse the ~/.seq24rc or ~/.config/sequencer64/sequencer64.rc file.

• bool write (const perform &perf)

This options-writing function is just about as complex as the options-reading function.

Private Member Functions

• bool error_message (const std::string §ionname)

Helper function for error-handling.

Additional Inherited Members

12.48.1 Detailed Description

The settings that are passed around are provided or used by the perform class.

12.48.2 Constructor & Destructor Documentation

12.48.2.1 seq64::optionsfile::optionsfile (const std::string & name)

Parameters

name	Provides the name of the options file; this is usually a full path file-specification.
------	--

12.48.2.2 seq64::optionsfile::∼optionsfile ()

12.48.3 Member Function Documentation

12.48.3.1 bool seq64::optionsfile::parse (perform & p) [virtual]

[midi-control]

Get the number of sequence definitions provided in the [midi-control] section. Ranges from 32 on up. Then read in all of the sequence lines. The first 32 apply to the first screen set. There can also be a comment line "# mute in group" followed by 32 more lines. Then there are addditional comments and single lines for BPM up, BPM down, Screen Set Up, Screen Set Down, Mod Replace, Mod Snapshot, Mod Queue, Mod Gmute, Mod Glearn, and Screen Set Play. These are all forms of MIDI automation useful to control the playback while not sitting near the computer.

[mute-group]

The mute-group starts with a line that indicates up to 32 mute-groups are defined. A common value is 1024, which means there are 32 groups times 32 keys. But this value is currently thrown away. This value is followed by 32 lines of data, each contained 4 sets of 8 settings. See the seq24-doc project on GitHub for a much more detailed description of this section.

[midi-clock]

The MIDI-clock section defines the clocking value for up to 16 output busses. The first number, 16, indicates how many busses are specified. Generally, these busses are shown to the user with names such as "[1] seq24 1".

[keyboard-control]

The keyboard control defines the keys that will toggle the stage of each of up to 32 patterns in a pattern/sequence box. These keys are displayed in each box as a reminder. The first number specifies the Key number, and the second number specifies the Sequence number.

[keyboard-group]

The keyboard group specifies more automation for the application. The first number specifies the Key number, and the second number specifies the Group number. This section should be better described in the seq24-doc project on GitHub.

[jack-transport]

This section covers various JACK settings, one setting per line. In order, the following numbers are specfied:

```
    jack_transport - Enable sync with JACK Transport.
    jack_master - Seq24 will attempt to serve as JACK Master.
    jack_master_cond - Seq24 will fail to be Master if there is already a Master set.
    song_start_mode:
    0 = Playback will be in Live mode. Use this to allow muting and unmuting of loops.
    1 = Playback will use the Song Editor's data.
```

[midi-input]

This section covers the MIDI input busses, and has a format similar to "[midi-clock]". Generally, these busses are shown to the user with names such as "[1] seq24 1", and currently there is only one input buss. The first field is the port number, and the second number indicates whether it is disabled (0), or enabled (1).

[midi-clock-mod-ticks]

This section covers.... One common value is 64.

[manual-alsa-ports]

This section covers.... Set to 1 if you want seq24 to create its own ALSA ports and not connect to other clients.

[last-used-dir]

This section simply holds the last path-name that was used to read or write a MIDI file. We still need to add a check for a valid path, and currently the path must start with a "/", so it is not suitable for Windows.

[interaction-method]

This section specified the kind of mouse interaction.

- 0 = 'seq24' (original Seq24 method).
- 1 = 'fruity' (similar to a certain fruity sequencer we like).

The second data line is set to "1" if Mod4 can be used to keep seq24 in note-adding mode even after the right-click is released, and "0" otherwise.

Parameters

p Provides the performance object to which all of these options apply.

Returns

Returns true if the file was able to be opened for reading. Currently, there is no indication if the parsing actually succeeded.

Implements seq64::configfile.

12.48.3.2 bool seq64::optionsfile::write (const perform & p) [virtual]

Parameters

р

Provides a const reference to the main perform object. However, we have to cast away the constness, because too many of the perform getter functions are used in non-const contexts.

Returns

Returns true if the write operations all succeeded.

New boolean to show sequence numbers; ignored in legacy mode.

Implements seq64::configfile.

12.48.3.3 bool seq64::optionsfile::error_message(const std::string & sectionname) [private]

Parameters

sectionname	Provides the name of the section for reporting the error.
-------------	---


Returns

Always returns false.

12.49 seq64::perfedit Class Reference

This class supports a Performance Editor that is used to arrange the patterns/sequences defined in the patterns panel.

Inheritance diagram for seq64::perfedit:



Public Member Functions

- perfedit (perform &p, bool second_perfedit=false, int ppqn=SEQ64_USE_DEFAULT_PPQN)

 Principal constructor, has a reference to a perform object.
- virtual ~perfedit ()

This rote constructor does nothing.

void init_before_show ()

This function forwards its call to the perfroll function of the same name.

void enqueue_draw (bool forward=true)

Helper wrapper for calling perfroll::queue_draw() for one or both perfedits.

void enregister_peer (perfedit *peer)

Register the peer perfedit object.

void set_zoom (int z)

Implements the horizontal zoom feature.

Static Public Member Functions

• static bool zoom_check (int z)

Checks zoom values for the z/Z keystrokes used in perfroll and perftime.

Private Member Functions

void set_beats_per_bar (int bpm)

Sets the beats-per-measure text and value to the given value, and then calls set_guides().

void set_beat_width (int bw)

Sets the BW (beat width, or the denominator in the time signature) text and values to the given value, and then calls set_guides().

void set_snap (int snap)

Sets the snap text and values to the given value, and then calls set_guides().

· void set_guides ()

Sets the guides, which are the L and R user-interface elements.

• void grow ()

Increments the size of the perfroll and perftime objects.

void set_looped ()

Set the looping in the perform object.

• void expand ()

Implement the expand action.

• void collapse ()

Implement the collapse action.

void copy ()

Implement the copy (actually, expand-and-copy) action.

• void undo ()

Implement the undo feature (Ctrl-Z).

void redo ()

Implement the redo feature (Ctrl-R).

• void popup menu (Gtk::Menu *menu)

Opens the given popup menu.

void draw_sequences ()

Forces a redraw of the sequences, though currently just the perfnames part of each sequence in the performance editor.

• bool timeout ()

Handles a drawing timeout.

void set_image (bool isrunning)

Changes the image used for the pause/play button.

· void start playing ()

Implement the playing.

void pause_playing ()

Pauses the playing of the song, leaving the progress bar where it stopped.

void stop_playing ()

Stop the playing.

void toggle_playing ()

Reverses the state of playback.

• void on_realize ()

This callback function calls the base-class on_realize() function, and then connects the perfedit::timeout() function to the Glib signal-timeout, with a redraw timeout of redraw_period_ms().

bool on_key_press_event (GdkEventKey *ev)

This function is the callback for a key-press event.

bool on_delete_event (GdkEventAny *)

All this callback function does is return false.

Private Attributes

• perfedit * m peer perfedit

The partner instance of perfedit.

• Gtk::Table * m_table

A whole horde of GUI elements.

Gtk::Adjustment * m_vadjust

Vertical adjust for piano roll.

Gtk::Adjustment * m hadjust

Horizontal adjust for piano roll.

Gtk::VScrollbar * m_vscroll

Vertical scroll for piano roll.

• Gtk::HScrollbar * m_hscroll

Horizonatl scroll for piano roll.

• perfnames * m_perfnames

Pattern names in leftmost column.

• perfroll * m_perfroll

The piano roll in the song editor.

• perftime * m_perftime

The time/measures bar above roll.

• Gtk::Menu * m_menu_snap

The menu for grid-snap selection.

• Gtk::Image * m_image_play

The image for the play button.

• Gtk::Button * m_button_snap

Button to bring up the snap menu.

• Gtk::Entry * m_entry_snap

Text edit for the grid-snap value.

• Gtk::Button * m_button_stop

The Stop Play button object.

Gtk::Button * m button play

Implements the yellow two-bar pause button.

• Gtk::ToggleButton * m_button_loop

Button for Left-to-Right looping.

• Gtk::Button * m button expand

Button for Left/Right expansion.

• Gtk::Button * m_button_collapse

Button for Left/Right collapse.

Gtk::Button * m_button_copy

Expand and copy between L/R.

• Gtk::Button * m button grow

Expand grid (bottom-right button).

• Gtk::Button * m_button_undo

Button to undo previous action.

• Gtk::Button * m button redo

Button to redo previous action.

Gtk::Button * m_button_bpm

Beats-per-measure menu button.

• Gtk::Entry * m_entry_bpm

Text-edit for beats-per-measure.

Gtk::Button * m_button_bw

Beat-width menu button.

• Gtk::Entry * m_entry_bw

Text-edit for beat-width.

Gtk::HBox * m hbox

Horizontal box (which?) in table.

• Gtk::HBox * m_hlbox

Horizontal box for buttons at top.

Gtk::Tooltips * m_tooltips

Container for tool-tips.

• Gtk::Menu * m_menu_bpm

Menus for time signature, beats per measure, beat width.

• Gtk::Menu * m_menu_bw

Drop-down menu for beat-width.

int m_snap

Sets the horizontal grid snap-to in units of "pulses" or "ticks".

• int m bpm

The current "beats per measure" value.

• int m bw

The current "beat width" value.

• int m ppqn

The current "parts per quarter note" value.

• bool m_is_running

Holds the current status of running, for use in display the play versus pause icon.

• int m_standard_bpm

The standard "beats per measure" of Sequencer64, which here matches the beats-per-measure displayed in the perfroll (piano roll).

Friends

• void update_perfedit_sequences ()

This global function in the seq64 namespace calls perfedit :: draw_sequences(), if the global perfedit objects exist.

Additional Inherited Members

12.49.1 Detailed Description

It has a seqroll and piano roll? No, it has a perform, a perfnames, a perfroll, and a perftime.

12.49.2 Constructor & Destructor Documentation

```
12.49.2.1 seq64::perfedit::perfedit ( perform & p, bool second_perfedit = false, int ppqn = SEQ64_USE_DEFAULT_PPQN )
```

We've reordered the pointer members and put them in the initializer list to make the constructor a bit cleaner.

Todo Offload most of the work into an initialization function like options does.

Parameters

p	Refers to the main performance object.	
second_perfedit	If true, this object is the second perfedit object.	
ppqn	The optionally-changed PPQN value to use for the performance editor.	

```
12.49.2.2 seq64::perfedit::~perfedit() [virtual]
```

We're going to have to run the application through valgrind to make sure that nothing is left behind.

12.49.3 Member Function Documentation

```
12.49.3.1 void seq64::perfedit::init_before_show()
```

It does not seem to need to also forward to the perftime function of the same name.

```
12.49.3.2 void seq64::perfedit::enqueue_draw ( bool forward = true )
```

Note that we call the children's queue_draw() functions, not enqueue_draw(), otherwise we'll get stack overflow.

Parameters

forward	If true (the default), pass the call to the peer. When passing this call to the peer, this parameter is set
	to false to prevent an infinite loop and the resultant stack overflow.

```
12.49.3.3 static bool seq64::perfedit::zoom_check(int z) [inline], [static]
```

It has to range from greater than 1 (the highest zoom-in causes an unexplained drawing artifact at this time), and not greater than four times the c_perf_scale_x value, at which point we have zoomed out so far that the measure numbers are almost completely obscured.

Parameters

7	The desired	zoom va	alue to	validate.
---	-------------	---------	---------	-----------

```
12.49.3.4 void seq64::perfedit::enregister_peer ( perfedit * peer ) [inline]
```

This function is meant to be called by mainwnd, which creates the perfedits and then makes sure they get along. Only the first call to this function will work; only one peer can be registered.

Parameters

peer	The peer perfedit object to register, if not null.
------	--

```
12.49.3.5 void seq64::perfedit::set_zoom ( int z )
```

```
12.49.3.6 void seq64::perfedit::set_beats_per_bar(int bpm) [private]
```

The usage of is modified was faulty. Offloaded it to the perform object to make it more foolproof. See the perform ::modify() function.

Parameters

bpm	Provides the beats/measure or beats/bar value to be set. This value is basically the numerator of the time
	signature.

```
12.49.3.7 void seq64::perfedit::set_beat_width(int bw) [private]
```

The usage of is modified was faulty. Offloaded it to the perform object to make it more foolproof. See the perform ::modify() function.

Parameters

bw | Provides the beat width to be set. The beat width is basically the denominator of the time signature.

```
12.49.3.8 void seq64::perfedit::set_snap ( int snap ) [private]
```

Parameters

snap Provide the snap value to be set. This value is basically the numerator of the expression "1 / snap".

```
12.49.3.9 void seq64::perfedit::set_guides( ) [private]
```

See the set_snap() function.

It's a little confusing; I assigned the label "m_standard_bpm" to the value 4 in "measure_pulse = $192 * 4 * m_bpm / m_bw$ ", but I am not sure I understand this equation... why the extra factor of 4? That 4 appears in "c_ppqn * 4" a lot in the original code.

```
12.49.3.10 void seq64::perfedit::grow() [private]
```

Make sure that setting the modified flag makes sense for this operation. It doesn't seem to modify members.

```
12.49.3.11 void seq64::perfedit::set_looped( ) [private]
12.49.3.12 void seq64::perfedit::expand( ) [private]
```

This action opens up a space of events between the L and R (left and right) markers. This action is preceded by pushing an Undo operation in the perform object, moving its triggers, and telling the perfoll to redraw.

```
12.49.3.13 void seq64::perfedit::collapse() [private]
```

This action removes all events between the L and R (left and right) markers. This action is preceded by pushing an Undo operation in the perform object, not moving its triggers (they go away), and telling the perfoll to redraw.

```
12.49.3.14 void seq64::perfedit::copy( ) [private]
```

This action opens up a space of events between the L and R (left and right) markers, and copies the information from the same amount of events that follow the R marker. This action is preceded by pushing an Undo operation in the perform object, copying its triggers, and telling the perfroll to redraw.

```
12.49.3.15 void seq64::perfedit::undo() [private]
```

We pop an Undo trigger, and then ask the perfroll to queue up a (re)drawing action.

```
12.49.3.16 void seq64::perfedit::redo( ) [private]
```

We pop an Redo trigger, and then ask the perfroll to queue up a (re)drawing action.

```
12.49.3.17 void seq64::perfedit::popup_menu ( Gtk::Menu * menu ) [private]
12.49.3.18 void seq64::perfedit::draw sequences ( ) [private]
```

This is meant to be called when the focus of an open segedit or eventedit window changes.

```
12.49.3.19 bool seq64::perfedit::timeout( ) [private]
```

It redraws "dirty" sequences in the perfroll and the perfnames objects, and shows draw progress on the perfroll. It also changes the pause/play image if the status of running has changed. This function is called frequently and continuously. It will work for both perfedit windows, if both are up.

```
12.49.3.20 void seq64::perfedit::set_image ( bool isrunning ) [private]
```

Parameters

isrunnina	If true, the image should be the pause image. Otherwise, it should be the play image.
	The state of the state of the paragraph of the state of th

```
12.49.3.21 void seq64::perfedit::start_playing( ) [private]
```

JACK will be used if it is present and, in the application, enabled and working.

```
12.49.3.22 void seq64::perfedit::pause_playing() [private]
```

Currently, it is just the same as stop_playing(), but we will get it to work. Keeps the stop button enabled as a kind of rewind for ALSA.

```
12.49.3.23 void seq64::perfedit::stop_playing() [private]
```

We need to make the progress line move back to the beginning right away here.

```
12.49.3.24 void seq64::perfedit::toggle_playing() [inline], [private]
```

Meant only to be called when the "Play" button is pressed. Currently, the GUI does not change. This function will ultimately act like a Pause/Play button, but currently the pause functionality on works (partially) for JACK transport. Currently not used.

```
12.49.3.25 void seq64::perfedit::on_realize( ) [private]
12.49.3.26 bool seq64::perfedit::on_key_press_event( GdkEventKey * ev ) [private]
```

By default, the space-bar starts the playing, and the Escape key stops the playing. The start/end key may be the same key (i.e. space-bar), allow toggling when the same key is mapped to both triggers. Note that we now pass false in the call to perform::playback_key_event(), if SEQ64_PAUSE_SUPPORT is compiled in. Song mode doesn't yield the pause effect we want.

Parameters

ev Provides the key event to implement.

```
12.49.3.27 bool seq64::perfedit::on_delete_event ( GdkEventAny * ) [inline], [private]
```

12.49.4 Friends And Related Function Documentation

```
12.49.4.1 void update_perfedit_sequences( ) [friend]
```

It is used by other objects (seqedit and eventedit) that can modify the currently-edited sequence shown in the perfedit (song window).

12.49.5 Field Documentation 12.49.5.1 perfedit* seq64::perfedit::m_peer_perfedit [private]

12.49.5.2 Gtk::Table* **seq64::perfedit::m_table** [private]

Layout table for song editor.

```
12.49.5.3 Gtk::Adjustment* seq64::perfedit::m_vadjust [private]
12.49.5.4 Gtk::Adjustment* seq64::perfedit::m_hadjust [private]
12.49.5.5 Gtk::VScrollbar* seq64::perfedit::m_vscroll [private]
12.49.5.6 Gtk::HScrollbar* seq64::perfedit::m_hscroll [private]
12.49.5.7 perfnames* seq64::perfedit::m_perfnames [private]
12.49.5.8 perfroll* seq64::perfedit::m_perfroll [private]
12.49.5.9 perftime* seq64::perfedit::m_perftime [private]
12.49.5.10 Gtk::Menu* seq64::perfedit::m_menu_snap [private]
12.49.5.11 Gtk::lmage* seq64::perfedit::m_image_play [private]
12.49.5.12 Gtk::Button* seq64::perfedit::m_button_snap [private]
12.49.5.13 Gtk::Entry* seq64::perfedit::m_entry_snap [private]
12.49.5.14 Gtk::Button* seq64::perfedit::m_button_stop [private]
12.49.5.15 Gtk::Button* seq64::perfedit::m_button_play [private]
```

The Play button object.

```
12.49.5.16 Gtk::ToggleButton* seq64::perfedit::m_button_loop [private]
12.49.5.17 Gtk::Button* seq64::perfedit::m_button_expand [private]
12.49.5.18 Gtk::Button* seq64::perfedit::m_button_collapse [private]
12.49.5.19 Gtk::Button* seq64::perfedit::m_button_copy [private]
12.49.5.20 Gtk::Button* seq64::perfedit::m_button_grow [private]
12.49.5.21 Gtk::Button* seq64::perfedit::m_button_undo [private]
12.49.5.22 Gtk::Button* seq64::perfedit::m_button_redo [private]
12.49.5.23 Gtk::Button* seq64::perfedit::m_button_bpm [private]
12.49.5.24 Gtk::Entry* seq64::perfedit::m_entry_bpm [private]
12.49.5.25 Gtk::Button* seq64::perfedit::m_button_bw [private]
12.49.5.26 Gtk::Entry* seq64::perfedit::m_entry_bw [private]
12.49.5.27 Gtk::HBox* seq64::perfedit::m_hbox [private]
12.49.5.28 Gtk::HBox* seq64::perfedit::m_hlbox [private]
12.49.5.29 Gtk::Tooltips* seq64::perfedit::m_tooltips [private]
12.49.5.30 Gtk::Menu* seq64::perfedit::m_menu_bpm [private]
Drop-down menu for beats/minute.
12.49.5.31 Gtk::Menu* seq64::perfedit::m_menu_bw [private]
12.49.5.32 int seq64::perfedit::m_snap [private]
12.49.5.33 int seq64::perfedit::m_bpm [private]
Do not confuse it with BPM (beats per minute). The numerator of the time signature.
12.49.5.34 int seq64::perfedit::m_bw [private]
```


Generated by Doxygen

The denominator of the time signature.

```
12.49.5.35 int seq64::perfedit::m_ppqn [private]
12.49.5.36 bool seq64::perfedit::m_is_running [private]
12.49.5.37 int seq64::perfedit::m_standard_bpm [private]
```

12.50 seq64::perfnames Class Reference

This class implements the left-side keyboard in the patterns window. Inheritance diagram for seq64::perfnames:



Public Member Functions

• perfnames (perform &p, perfedit &parent, Gtk::Adjustment &vadjust)

Principal constructor for this user-interface object.

virtual ∼perfnames ()

Let's provide a do-nothing virtual destructor.

• void redraw_dirty_sequences ()

Redraws sequences that have been modified.

Private Member Functions

void enqueue_draw ()

Wraps queue_draw() and forwards the call to the parent perfedit, so that it can forward it to any other perfedit that exists, and to the other sub-elements of the song editor.

• int convert_y (int y)

Converts a y-value into a sequence number and returns it.

void draw sequences ()

New function to encapsulate forced redrawing of all sequence names in the current viewport.

void draw_sequence (int sequence)

Draw the given sequence.

void change_vert ()

Change the vertial offset of a sequence/pattern.

· void redraw (int sequence)

Redraw the given sequence.

void on_realize ()

Handles the callback when the window is realized.

• bool on_expose_event (GdkEventExpose *ev)

Handles an on-expose event.

• bool on button press event (GdkEventButton *ev)

Provides the callback for a button press, and it handles only a left mouse button [the right mouse button is handled in on_button_release_event()].

bool on_button_release_event (GdkEventButton *ev)

Handles a button-release for the right button, bringing up a popup menu that is identical to the right-click popup menu for a slot in the patterns panel (mainwid), and context sensitive.

void on_size_allocate (Gtk::Allocation &)

Handles a size-allocation event.

• bool on_scroll_event (GdkEventScroll *ev)

Handle the vertical scrolling of the window.

Private Attributes

· perfedit & m_parent

Provides a link to the perfedit that created this object.

· int m names chars

Provides the number of the characters in the name box.

int m_char_w

Provides the "real" width of a character.

· int m setbox w

Provides the width of the "set number" box.

int m_namebox_w

Provides the width of the "name" box.

• int m_names_x

Provides the width of the names box, which is the width of a character for 24 characters.

· int m names y

Provides the height of the names box, which is hardwired to 24 pixels.

· int m_xy_offset

Provides the horizontal and vertical offsets of the text relative to the names box.

· const int m seqs in set

The number of sequences in a set, currently still hardwired to 32.

• const int m_sequence_max

The maximum number of sequences, current $32 \times 32 = 1024$.

• int m_sequence_offset

The offset from the 0th sequence, which is determined by the vertical view of the piano roll, controlled by the vertical scroll-bar.

• bool m sequence active [c max sequence]

Indicates if the given sequence is active or not.

Friends

· class perfedit

Additional Inherited Members

12.50.1 Detailed Description

It inherits from gui_drawingarea_gtk2 to support the font, color, and other GUI functionality, and from seqmenu to support the right-click Edit/New/Cut right-click menu.

Obsolete Note the usage of virtual base classes. Since these can add some extra overhead, we should determine if we can do without the virtuality (and indeed it doesn't seem to be needed).

12.50.2 Constructor & Destructor Documentation

12.50.2.1 seq64::perfnames::perfnames (perform & p, perfedit & parent, Gtk::Adjustment & vadjust)

Weird is that the window (x,y) are set to (c_names_x, 100), when c_names_y is 22 (now 24) in globals.h.

Parameters

р	Provides a reference to the main performance object of the application.
parent	Provides a reference to the object that contains this object, so that this object can tell the parent to queue up a drawing operation.
vadjust	Provides the vertical scrollbar object needed so that perfnames can respond to scrollbar cursor/thumb movement.

12.50.2.2 virtual seq64::perfnames::~perfnames() [inline], [virtual]

12.50.3 Member Function Documentation

```
12.50.3.1 void seq64::perfnames::redraw_dirty_sequences( )
12.50.3.2 void seq64::perfnames::enqueue_draw( ) [private]
```

The parent perfedit will call perfnames::queue_draw() on behalf of this object, and it will pass a perfnames ∴:enqueue draw() to the peer perfedit's perfnames, if the peer exists.

```
12.50.3.3 int seq64::perfnames::convert_y ( int y ) [private]
```

Used in figuring out which sequence to mute/unmute in the performance editor.

Parameters

y The y value (within the vertical limits of the perfnames column to the left of the performance editor's piano roll.

Returns

Returns the sequence number corresponding to the y value.

```
12.50.3.4 void seq64::perfnames::draw_sequences( ) [private]
12.50.3.5 void seq64::perfnames::draw_sequence(int seqnum) [private]
```

This function has to be prepared to handle an almost endless list of sequences, including unused ones, to draw them all with compatible styles. The sequences are grouped by set-number. The set-number occurs every 32 sequences in the leftmost column of the window.

- 1. Render the set number, or a blank box, in leftmost column. If the y height of the first draw_rectangle is m_names_y + 1, then we get a black line for the blank tracks, looks ugly.
- 2. Make sure that the rectangle drawn with the proper background colors for various combinations of muting and highlighting, otherwise just the name is properly colored.
- 3. Render the column with the name of the sequence. The channel number ranges from 1 to 16, but SMF 0 is indicated on-screen by a channel number of 0. We get the label format from the perform object, for consistency across windows.

Parameters

seqnum Index to the sequence information to be drawn.

```
12.50.3.6 void seq64::perfnames::change_vert( ) [private]
```

```
12.50.3.7 void seq64::perfnames::redraw(int sequence) [inline], [private], [virtual]
```

This function is a virtual function of segmenu that must be overridden in this class.

Parameters

```
sequence Provides the number of the sequence to be redrawn.
```

Implements seq64::segmenu.

```
12.50.3.8 void seq64::perfnames::on_realize( ) [private]
```

It first calls the base-class version of on_realize(). Then it allocates any additional resources needed.

```
12.50.3.9 bool seq64::perfnames::on_expose_event ( GdkEventExpose * ev ) [private]
```

It draws all of the sequences that will be visible.

We could actually optimize this a tiny bit, to save some additions in the for loop.

Parameters

```
ev The expose event, not used.
```

Returns

Always returns true.

```
12.50.3.10 bool seq64::perfnames::on_button_press_event( GdkEventButton * ev ) [private]
```

Two operations are supported by left-clicking on the sequence/track name:

```
    Normal. Toggles the mute status of the sequence that is clicked.
    Shift. Toggles the mutes status of all other sequences, making this operation an easy way to preview a single sequence in the
```

performance editor, then bring back the rest of the tracks.

Parameters

```
ev The mouse button event.
```

Returns

Always returns true.

12.50.3.11 bool seq64::perfnames::on_button_release_event(GdkEventButton * p0) [private]

```
p0 The button event.
```

Returns

Always returns false.

12.50.3.12 void seq64::perfnames::on_size_allocate (Gtk::Allocation & a) [private]

It first calls the base-class version of this function.

Parameters

The allocation event. It is passed to the base-class on_size_allocate() function, and then m_window_x and m_window_y are set to the width and height, respectively, of the allocation.

12.50.3.13 bool seq64::perfnames::on_scroll_event(GdkEventScroll * ev) [private]

The vertical value is incremented or decremented by the amount of the step increment, and the page is clamped to the new value.

Parameters

ev The scrolling event.

Returns

Always returns true.

12.50.4 Friends And Related Function Documentation

12.50.4.1 friend class perfedit [friend]

12.50.5 Field Documentation

12.50.5.1 perfedit& seq64::perfnames::m_parent [private]

We want to support two perfedit windows, but the children of perfedit will have to communicate changes requiring a redraw through the parent.

12.50.5.2 int seq64::perfnames::m_names_chars [private]

Pretty much hardwired to 24 at present.

```
12.50.5.3 int seq64::perfnames::m_char_w [private]
```

This value is obtained from a font-renderer accessor function.

```
12.50.5.4 int seq64::perfnames::m_setbox_w [private]
```

This used to be hardwired to 6 * 2 (character-width times two).

```
12.50.5.5 int seq64::perfnames::m_namebox_w [private]
```

This used to be a weird calculation based on character width.

```
12.50.5.6 int seq64::perfnames::m_names_x [private]
```

```
12.50.5.7 int seq64::perfnames::m_names_y [private]
```

This value was once 22 pixels, but we need a little extra room for our new font. This extra room is compatible enough with the old font, as well.

```
12.50.5.8 int seq64::perfnames::m_xy_offset [private]
```

Currently hardwired.

```
12.50.5.9 const int seq64::perfnames::m_seqs_in_set [private]
```

```
12.50.5.10 const int seq64::perfnames::m_sequence_max [private]
```

```
12.50.5.11 int seq64::perfnames::m_sequence_offset [private]
```

```
12.50.5.12 bool seq64::perfnames::m_sequence_active[c_max_sequence] [private]
```

If this really is the true meaning of this value, we ought to get it directly from the sequence if we can.

12.51 seg64::perform Class Reference

This class supports the performance mode.

Public Types

Public Member Functions

• perform (gui_assistant &mygui, int ppqn=SEQ64_USE_DEFAULT_PPQN)

This construction initializes a vast number of member variables, some of them public (but we're working on that)!

~perform ()

The destructor sets some running flags to false, signals this condition, then joins the input and output threads if the were launched.

• bool is_modified () const

'Getter' function for member m is modfied

· void modify ()

'Setter' function for member m_is_modified This setter only sets the modified-flag to true.

• int sequence_count () const

'Getter' function for member m_sequence_count It is better to call this getter before bothering to even try to use a sequence.

int sequence_max () const

'Getter' function for member m_sequence_max

• bool is_control_status () const

'Getter' function for member m_control_status

void set_edit_sequence (int seqnum)

'Setter' function for member m_edit_sequence

void unset_edit_sequence (int seqnum)

'Setter' function for member m_edit_sequence

• bool is_edit_sequence (int seqnum) const

'Getter' function for member m_edit_sequence

• int get_beats_per_bar () const

'Getter' function for member m_beats_per_bar

void set_beats_per_bar (int bpm)

'Setter' function for member m beats per bar

int get_beat_width () const

'Getter' function for member m_beat_width

void set_beat_width (int bw)

'Setter' function for member m_beat_width

void clocks_per_metronome (int cpm)

'Setter' function for member m_clocks_per_metronome

• int clocks_per_metronome () const

'Getter' function for member m_clocks_per_metronome

void set_32nds_per_quarter (int tpq)

'Setter' function for member m_32nds_per_quarter

• int get_32nds_per_quarter () const

'Getter' function for member m_32nds_per_quarter

void us_per_quarter_note (long upqn)

'Setter' function for member m_us_per_quarter_note

· long us per quarter note () const

'Getter' function for member m_us_per_quarter_note

• const gui_assistant & gui () const

'Getter' function for member m_gui_support The const getter.

• gui assistant & gui ()

'Getter' function for member m_gui_support The un-const getter.

const keys_perform & keys () const

'Getter' function for member m_gui_support.keys() The const getter.

keys_perform & keys ()

'Getter' function for member m_gui_support.keys() The un-const getter.

· mastermidibus & master bus ()

'Getter' function for member m_master_bus

void filter_by_channel (bool flag)

'Setter' function for member m_master_bus.filter_by_channel()

bool is_running () const

'Getter' function for member m_running Could also be called "is_playing()".

• bool is_pattern_playing () const

'Setter' function for member m is pattern playing

bool toggle_song_start_mode ()

'Setter' function for member m_song_start_mode

void song_start_mode (bool flag)

'Setter' function for member m song start mode

bool song_start_mode () const

'Getter' function for member m_song_start_mode

bool is jack running () const

'Getter' function for member m_jack_asst.is_running() This function is useful for announcing the status of JACK in user-interface items that only have access to the perform object.

• bool is_jack_master () const

'Getter' function for member m_jack_asst.is_master()

• bool is_paused () const

'Getter' function for member m_is_paused

bool is_pausable () const

 ${\it 'Getter' function for member m_is_paused and ! m_jack_asst.is_running() We might just make this internal.}$

void enregister (performcallback *pfcb)

Adds a pointer to an object to be notified by this perform object.

bool clear_all ()

Clears all of the patterns/sequences.

void launch (int ppqn)

Calls the MIDI buss and JACK initialization functions and the input/output thread-launching functions.

• void new_sequence (int seq)

Creates a new pattern/sequence for the given slot, and sets the new pattern's master MIDI bus address.

void add_sequence (sequence *seq, int perf)

Adds a pattern/sequence pointer to the list of patterns.

void delete_sequence (int seq)

Deletes a pattern/sequence by number.

bool is_sequence_in_edit (int seq)

Check if the pattern/sequence, given by number, has an edit in progress.

• void clear_sequence_triggers (int seq)

Clears the patterns/sequence for the given sequence, if it is active.

· void print_triggers () const

Shows all the triggers of all the sequences.

• void finish ()

The rough opposite of launch(); it doesn't stop the threads.

midipulse get_tick () const

'Getter' function for member m tick

· midipulse get jack tick () const

'Getter' function for member m_jack_tick

void set_jack_tick (midipulse tick)

'Setter' function for member m_jack_tick

void set_left_tick (midipulse tick, bool setstart=true)

Set the left marker at the given tick.

· midipulse get_left_tick () const

'Getter' function for member m_left_tick

void set_start_tick (midipulse tick)

'Setter' function for member m_starting_tick

· midipulse get start tick () const

'Setter' function for member m_starting_tick

• void set_right_tick (midipulse tick, bool setstart=true)

Set the right marker at the given tick.

· midipulse get_right_tick () const

'Getter' function for member m_right_tick

• double left_right_size () const

Convenience function for JACK support when loop in song mode.

void move_triggers (bool direction)

If the left tick is less than the right tick, then, for each sequence that is active, its triggers are moved by the difference between the right and left in the specified direction.

· void copy_triggers ()

If the left tick is less than the right tick, then, for each sequence that is active, its triggers are copied, offset by the difference between the right and left.

void push_trigger_undo (int track=SEQ64_ALL_TRACKS)

For every active sequence, call that sequence's push_trigger_undo() function.

• void pop_trigger_undo ()

For every active sequence, call that sequence's pop_trigger_undo() function.

- void pop_trigger_redo ()
- bool have_undo () const

'Getter' function for member m_have_undo

- void set_have_undo (bool undo)
- bool have_redo () const

'Getter' function for member m_have_redo

void set_have_redo (bool redo)

'Setter' function for member m_have_redo

• void split_trigger (int seqnum, midipulse tick)

Convenience function for perfroll's split-trigger functionality.

midipulse get_max_trigger ()

Locates the largest trigger value among the active sequences.

• void collapse ()

Convenience function for perfedit's collapse functionality.

· void copy ()

Convenience function for perfedit's copy functionality.

· void expand ()

Convenience function for perfedit's expand functionality.

midi_control & midi_control_toggle (int seq)

Retrieves a reference to a value from m_midi_cc_toggle[].

midi_control & midi_control_on (int seq)

Retrieves a reference to a value from m_midi_cc_on[].

midi_control & midi_control_off (int seq)

Retrieves a reference to a value from m_midi_cc_off[].

• void handle midi control (int control, bool state)

Handle the MIDI Control values that provide some automation for the application.

const std::string & get_screen_set_notepad (int screen_set) const

Retrieves the given string from m_screen_set_notepad[].

• const std::string & current_screen_set_notepad () const

Returns the notepad text for the current screen-set.

void set_screen_set_notepad (int screenset, const std::string ¬e)

Copies the given string into m_screen_set_notepad[].

void set_screen_set_notepad (const std::string ¬e)

Sets the notepad text for the current screen-set.

int get_screenset () const

'Getter' function for member m screenset

• void set_playing_screenset ()

Sets the screen set that is active, based on the value of m_screenset.

• void set_screenset (int ss)

Sets the m_screenset value (the index or ID of the current screen set).

• int get_playing_screenset () const

'Getter' function for member m_playing_screen

· bool any_group_unmutes () const

'Getter' function for member m mute group[] Returns true if there are any unmute statuses in the mute-group array.

void mute_group_tracks ()

If m_mode_group is true, then this function operates.

void select_and_mute_group (int g_group)

Select a mute group and then mutes the track in the group.

void set_song_mute (mute_op_t op)

Provides for various settings of the song-mute status of all sequences in the song.

void set mode group mute ()

'Setter' function for member m mode group

void unset_mode_group_mute ()

'Setter' function for member m_mode_group Unsets this member.

void select_group_mute (int g_mute)

If we're in group-learn mode, then this function gets the playing statuses of all of the sequences in the current playscreen, and copies them into the desired mute-group.

void set_mode_group_learn ()

Sets the group-mute mode, then the group-learn mode, then notifies all of the notification subscribers.

void unset_mode_group_learn ()

Notifies all of the notification subscribers that group-learn is being turned off.

- bool is_group_learning ()
- void set_and_copy_mute_group (int group)

When in group-learn mode, for active sequences, the mute-group settings are set based on the playing status of each sequence.

• void start (bool state)

If JACK is not running, call inner_start() with the given state.

• void stop ()

If JACK is not running, call inner_stop().

void start_jack ()

If JACK is supported, starts the JACK transport.

void stop_jack ()

If JACK is supported, stops the JACK transport.

void position_jack (bool state)

If JACK is supported and running, sets the position of the transport.

• void off sequences ()

For all active patterns/sequences, set the playing state to false.

void all_notes_off ()

For all active patterns/sequences, turn off its playing notes.

· void set active (int seq, bool active)

Sets or unsets the active state of the given pattern/sequence number.

void set_was_active (int seq)

Sets was-active flags: main, edit, perf, and names.

· bool is_dirty_main (int seq)

Checks the pattern/sequence for main-dirtiness.

bool is_dirty_edit (int seq)

Checks the pattern/sequence for edit-dirtiness.

• bool is_dirty_perf (int seq)

Checks the pattern/sequence for perf-dirtiness.

• bool is_dirty_names (int seq)

Checks the pattern/sequence for names-dirtiness.

• bool is_active (int seq) const

Checks the pattern/sequence for activity.

const sequence * get_sequence (int seq) const

Retrieves the actual sequence, based on the pattern/sequence number.

• sequence * get_sequence (int seq)

Retrieves the actual sequence, based on the pattern/sequence number.

• bool is_exportable (int seq) const

Indicates that the desired sequence is active, unmuted, and has a non-zero trigger count.

void reset_sequences (bool pause=false)

For all active patterns/sequences, get its playing state, turn off the playing notes, set playing to false, zero the markers, and, if not in playback mode, restore the playing state.

void play (midipulse tick)

Plays all notes to the current tick.

void set_orig_ticks (midipulse tick)

For every pattern/sequence that is active, sets the "original tick" value for the pattern.

void set_beats_per_minute (int bpm)

Sets the value of the BPM into the master MIDI buss, after making sure it is squelched to be between 20 and 500.

int get_beats_per_minute ()

'Getter' function for member m_master_bus.get_beats_per_minute Retrieves the BPM setting of the master MIDI buss.

void set_looping (bool looping)

'Setter' function for member m_looping

• void set_sequence_control_status (int status)

If the given status is present in the c_status_snapshot, the playing state is saved.

void unset_sequence_control_status (int status)

If the given status is present in the c_status_snapshot, the playing state is restored.

void sequence_playing_toggle (int seq)

If the given sequence is active, then it is toggled.

· void sequence_playing_change (int seq, bool on)

Turn the playing of a sequence on or off, if it is active.

void sequence playing on (int seq)

Calls sequence_playing_change() with a value of true.

void sequence_playing_off (int seq)

Calls sequence_playing_change() with a value of false.

· void mute all tracks (bool flag=true)

Mutes/unmutes all tracks in the current set of active patterns/sequences.

• void toggle_all_tracks ()

Toggles the mutes status of all tracks in the current set of active patterns/sequences.

void mute_screenset (int ss, bool flag=true)

Mutes/unmutes all tracks in the desired screen-set.

void output func ()

Performance output function.

void input_func ()

This function is called by input_thread_func().

void set group mute state (int gtrack, bool muted)

This function sets the mute state of an element in the m_mute_group array.

bool get_group_mute_state (int gtrack)

The opposite of set_group_mute_state(), it gets the value of the desired track.

void set offset (int offset)

Calculates the offset into the screen sets.

• int get_offset () const

'Getter' function for member m offset

void save_playing_state ()

For all active patterns/sequences, this function gets the playing status and saves it in m_sequence_state[i].

· void restore_playing_state ()

For all active patterns/sequences, this function gets the playing status from m_sequence_state[i] and sets it for the sequence.

std::string key_name (unsigned int k) const

Here follows a few forwarding functions for the keys perform-derived classes.

keys_perform::SlotMap & get_key_events ()

Forwarding function for key events.

• keys_perform::SlotMap & get_key_groups ()

Forwarding function for key groups.

keys_perform::RevSlotMap & get_key_events_rev ()

Forwarding function for reverse key events.

keys_perform::RevSlotMap & get_key_groups_rev ()

Forwarding function for reverse key groups.

bool show_ui_sequence_key () const

'Getter' function for member m_show_ui_sequency_key Provides access to keys().show_ui_sequence_key().

void show_ui_sequence_key (bool flag)

'Setter' function for member m_show_ui_sequency_key

bool show_ui_sequence_number () const

'Getter' function for member m_show_ui_sequency_number Provides access to keys().show_ui_sequence_number().

void show_ui_sequence_number (bool flag)

'Getter' function for member m_show_ui_sequency_number

unsigned int lookup_keyevent_key (int seqnum)

Gets the event key for the given sequence.

long lookup_keyevent_seq (unsigned int keycode)

Gets the sequence number for the given event key.

unsigned int lookup_keygroup_key (long groupnum)

Gets the group key for the given sequence.

long lookup_keygroup_group (unsigned int keycode)

Gets the group number for the given group key.

void start_playing (bool songmode=false)

Encapsulates a series of calls used in mainwnd.

• void pause_playing ()

Pause playback, so that progress bars stay where they are, and playback always resumes where it left off, even in ALSA mode.

void stop_playing ()

Encapsulates a series of calls used in mainwnd.

void start key (bool songmode=false)

Invoke the start key functionality.

void pause_key (bool songmode=false)

Invoke the pause key functionality.

void stop_key ()

Invoke the stop key functionality.

void learn_toggle ()

Encapsulates some calls used in mainwnd.

• int decrement beats per minute ()

Encapsulates some calls used in mainwnd.

int increment_beats_per_minute ()

Encapsulates some calls used in mainwnd.

int decrement_screenset ()

Encapsulates some calls used in mainwnd.

int increment_screenset ()

Encapsulates some calls used in mainwnd.

bool highlight (const sequence &seq) const

True if a sequence is empty and should be highlighted.

bool is_smf_0 (const sequence &seq) const

True if the sequence is an SMF 0 sequence.

void sequence_key (int seq)

Handle a sequence key to toggle the playing of an active pattern in the selected screen-set.

std::string sequence_label (const sequence &seq)

Provides a way to format the sequence parameters string for display in the mainwid or perfnames modules.

void set_input_bus (int bus, bool input_active)

Sets the input bus, and handles the special "key labels on sequence" and "sequence numbers on sequence" functionality.

• bool mainwnd_key_event (const keystroke &k)

Provided for mainwnd :: on_key_press_event() and mainwnd :: on_key_release_event() to call.

• bool perfroll_key_event (const keystroke &k, int drop_sequence)

Provided for perfroll :: on_key_press_event() and perfroll :: on_key_release_event() to call.

bool playback_key_event (const keystroke &k, bool songmode=false)

New function provided to unify the stop/start (space/escape) behavior of the various windows where playback can be started, paused, or stopped.

Private Member Functions

· int max active set () const

Checks the whole universe of sequences to determine the current last-active set, that is, the highest set that has any active sequences in it.

void launch_input_thread ()

Creates the input thread using input_thread_func().

• void launch output thread ()

Creates the output thread using output_thread_func().

bool init_jack ()

Initializes JACK support, if SEQ64_JACK_SUPPORT is defined.

• bool deinit jack ()

Tears down the JACK infrastructure.

• bool seq_in_playing_screen (int seq)

A helper function for determining if the mode group is in force, the playing screenset is the same as the current screenset, and the sequence is in the range of the playing screenset.

void is modified (bool flag)

'Setter' function for member m_is_modified

· bool is_midi_control_valid (int seq) const

Checks the parameter against c_midi_controls.

bool is_screenset_valid (int screenset) const

Checks the screenset against m_max_sets.

void set running (bool running)

'Setter' function for member m_running

void is_pattern_playing (bool flag)

'Setter' function for member m is pattern playing

void set_playback_mode (bool playbackmode)

'Setter' function for member m_playback_mode

int mute group offset (int track)

A helper function to calculate the index into the mute-group array, based on the desired track.

bool is_seq_valid (int seq) const

Provides common code to check for the bounds of a sequence number.

• bool is mseq valid (int seq) const

Validates the sequence number, which is important since they're currently used as array indices.

bool install_sequence (sequence *seq, int seqnum)

A private helper function for add sequence() and new sequence().

void inner_start (bool state)

Locks on m_condition_var.

void inner_stop (bool midiclock=false)

Unconditionally, and without locking, clears the running status, resets the sequences, and sets m_usemidiclock false.

int clamp_track (int track) const

Provides common code to keep the track value valid.

• void set_all_key_events ()

Pass-along function for keys().set_all_key_events.

void set_all_key_groups ()

Pass-along function for keys().set_all_key_events.

void set_key_event (unsigned int keycode, long sequence_slot)

At construction time, this function sets up one keycode and one event slot.

void set_key_group (unsigned int keycode, long group_slot)

At construction time, this function sets up one keycode and one group slot.

Private Attributes

• bool m_song_start_mode

If true, playback is done in Song mode, not Live mode.

gui_assistant & m_gui_support

Support for a wide range of GUI-related operations.

bool m_mute_group [c_gmute_tracks]

Mute group support.

bool m_tracks_mute_state [c_seqs_in_set]

Holds the current mute states of each track.

· bool m mode group

If true, indicates that a mode group is selected, and playing statuses will be "memorized".

• bool m_mode_group_learn

If true, indicates that a group learn is selected, which also "memorizes" a mode group, and notifies subscribers of a group-learn change.

int m_mute_group_selected

Selects a group to mute.

· int m_playing_screen

Playing screen support.

· int m_playscreen_offset

Playing screen sequence number offset.

• sequence * m_seqs [c_max_sequence]

Provides a "vector" of patterns/sequences.

• bool m_seqs_active [c_max_sequence]

Each boolean value in this array is set to true if a sequence is active, meaning that it will be used to hold some kind of MIDI data, even if only Meta events.

• bool m was active main [c max sequence]

Each boolean value in this array is set to true if a sequence was active, meaning that it was found to be active at the time we were setting it to inactive.

bool m_was_active_edit [c_max_sequence]

Each boolean value in this array is set to true if a sequence was active, meaning that it was found to be active at the time we were setting it to inactive.

bool m_was_active_perf [c_max_sequence]

Each boolean value in this array is set to true if a sequence was active, meaning that it was found to be active at the time we were setting it to inactive.

• bool m was active names [c max sequence]

Each boolean value in this array is set to true if a sequence was active, meaning that it was found to be active at the time we were setting it to inactive.

• bool m sequence state [c max sequence]

Saves the current playing state of each pattern.

· mastermidibus m master bus

Provides our MIDI buss.

pthread_t m_out_thread

Provides information for managing pthreads.

pthread_t m_in_thread

Provides a "handle" to the input thread.

bool m_out_thread_launched

Indicates that the output thread has been started.

· bool m_in_thread_launched

Indicates that the input thread has been started.

• bool m_running

Indicates that playback is running.

· bool m_is_pattern_playing

Indicates that a pattern is playing.

bool m_inputing

Indicates that events are being written to the MIDI input busses in the input thread.

bool m_outputing

Indicates that events are being written to the MIDI output busses in the output thread.

bool m looping

Indicates that status of the "loop" button in the performance editor.

bool m_playback_mode

Specifies the playback mode.

• int m ppqn

Holds the current PPQN for usage in various actions.

• int m_beats_per_bar

Holds the beats/bar value as obtained from the MIDI file.

int m_beat_width

Holds the beat width value as obtained from the MIDI file.

· int m clocks per metronome

Augments the beats/bar and beat-width with the additional values included in a Time Signature meta event.

int m_32nds_per_quarter

Augments the beats/bar and beat-width with the additional values included in a Time Signature meta event.

long m_us_per_quarter_note

Augments the beats/bar and beat-width with the additional values included in a Tempo meta event.

midipulse m_one_measure

Holds the "one measure's worth" of pulses (ticks), which is normally m ppgn * 4.

midipulse m_left_tick

Holds the position of the left (L) marker, and it is first defined as 0.

• midipulse m_right_tick

Holds the position of the right (R) marker, and it is first defined as the end of the fourth measure.

· midipulse m starting tick

Holds the starting tick for playing.

midipulse m_tick

MIDI Clock support.

· midipulse m jack tick

Let's try to save the last JACK pad structure tick for re-use with resume after pausing.

· bool m_usemidiclock

More MIDI clock support.

bool m_midiclockrunning

More MIDI clock support.

• int m_midiclocktick

More MIDI clock support.

int m_midiclockpos

More MIDI clock support.

· bool m is paused

Support for pause, which does not reset the "last tick" when playback stops/starts.

std::string m_screen_set_notepad [c_max_sets]

Used in the mainwnd class to set the notepad text for the given set.

midi_control m_midi_cc_toggle [c_midi_controls]

Provides the settings of MIDI Toggle, as read from the "rc" file.

• midi_control m_midi_cc_on [c_midi_controls]

Provides the settings of MIDI On, as read from the "rc" file.

midi_control m_midi_cc_off [c_midi_controls]

Provides the settings of MIDI Off, as read from the "rc" file.

· int m offset

Holds the current offset into the screen-sets.

int m_control_status

Holds the OR'ed control status values.

• int m_screenset

Indicates the number of the currently-selected screen-set.

· int m_seqs_in_set

We will eventually replace c_seqs_in_set with this member, which defaults to the value of c_seqs_in_set.

int m_max_sets

A replacement for the c_max_sets constant.

• int m_sequence_count

Keeps track of created sequences, whether or not they are active.

• int m_sequence_max

A replacement for the c_max_sequence constant.

• int m_edit_sequence

Hold the number of the currently-in-edit sequence.

• bool m_is_modified

It may be a good idea to eventually centralize all of the dirtiness of a performance here.

• condition_var m_condition_var

A condition variable to protect playback.

· jack_assistant m_jack_asst

A wrapper object for the JACK support of this application.

- · bool m have undo
- std::vector< int > m_undo_vect

Holds ??? for undo operations.

- bool m have redo
- std::vector< int > m_redo_vect

Holds ??? for undo operations.

std::vector< performcallback * > m_notify

Static Private Attributes

• static midi_control sm_mc_dummy

Provides a static self-reference to the one and only perform object that exists in the application, for use in callbacks that do not support object pointers and require non-member functions.

Friends

- · class jack assistant
- · class keybindentry
- · class midifile
- · class optionsfile
- · class options
- int jack sync callback (jack transport state t state, jack position t *pos, void *arg)

Global functions for JACK support and JACK sessions.

12.51.1 Detailed Description

It has way too many data members, one of them public. Might be ripe for refactoring. That has its own dangers, of course.

12.51.2 Member Enumeration Documentation

12.51.2.1 enum seq64::perform::mute_op_t

Enumerator

MUTE_TOGGLE
MUTE_OFF
MUTE_ON

```
12.51.2.2 enum seq64::perform::ff_rw_button_t
```

Enumerator

FF_RW_REWIND FF_RW_NONE FF_RW_FORWARD

12.51.3 Constructor & Destructor Documentation

```
12.51.3.1 seq64::perform::perform ( gui_assistant & mygui, int ppqn = SEQ64_USE_DEFAULT_PPQN )
```

Also note that we have a little issue with the fact that various sequences (patterns) can potentially have different beats/measure and beat-width values.

Currently, when reading the MIDI file, the beats/minute value is obtained from the MIDI file, if present, and this value is passed to perform::set_beats_per_minute(), which forwards it to the master MIDI buss and JACK assistant objects. This Tempo setting comes from both the Tempo meta event in track 0, and from the Seq24's c_bpm SeqSpec section! This setting is now also made for the two Time Signature values.

Parameters

mygui	Provides access to the GUI assistant that holds many things, including the containers of keys and the
	"events" they provide. This is a base-class reference; for a real class, see the gui_assistant_gtk2 class
	in the seq_gtkmm2 GUI-specific library. Note that we access the m_gui_support member using the
	gui() accessor function.
ppqn	The default, choosable, or actual PPQN value.

```
12.51.3.2 seq64::perform::\simperform ( )
```

Finally, any active or inactive (but allocated) patterns/sequences are deleted, and their pointers nullified.

12.51.4 Member Function Documentation

```
12.51.4.1 bool seq64::perform::is_modified( ) const [inline]
12.51.4.2 void seq64::perform::modify( ) [inline]
```

The setter that will, is_modified(), is private. No one but perform and its friends should falsify this flag.

```
12.51.4.3 int seq64::perform::sequence_count() const [inline]
```

In many cases at startup, or when loading a file, there are no sequences yet, and still the code calls functions that try to access them.

```
12.51.4.4 int seq64::perform::sequence_max() const [inline]
```

12.51.4.5 bool seq64::perform::is_control_status() const [inline]

Returns

Returns true if the m_control_status value is non-zero, which means that there is a queue, replace, or snapshot functionality in progress.

12.51.4.6 void seq64::perform::set_edit_sequence (int seqnum) [inline]

Parameters

seqnum	Pass in -1 to disable the edit-sequence number unconditionally. Use unset_edit_sequence() to
	disable it if it matches the current edit-sequence number.

12.51.4.7 void seq64::perform::unset_edit_sequence(int seqnum) [inline]

Disables the edit-sequence number if it matches the parameter.

Parameters

seqnum	The sequence number of the sequence to unset.
--------	---

12.51.4.8 bool seq64::perform::is_edit_sequence (int seqnum) const [inline]

Parameters

seqnum	Tests the parameter against m_edit_sequence. Returns true if that member is not -1, and the
	parameter matches it.

12.51.4.9 int seq64::perform::get_beats_per_bar() const [inline]

12.51.4.10 void seq64::perform::set_beats_per_bar(int bpm) [inline]

Parameters

bpm	Provides the value for beats/measure. A	Also used to set the beats/measure in the JACK assistant object.
-----	---	--

12.51.4.11 int seq64::perform::get_beat_width() const [inline]

12.51.4.12 void seq64::perform::set_beat_width(int bw) [inline]

Provides the value for beat-width. Also used to set the beat-width in the JACK assistant object.

```
12.51.4.13 void seq64::perform::clocks_per_metronome(int cpm) [inline]
12.51.4.14 int seq64::perform::clocks_per_metronome() const [inline]
12.51.4.15 void seq64::perform::set_32nds_per_quarter(int tpq) [inline]
12.51.4.16 int seq64::perform::get_32nds_per_quarter( ) const [inline]
12.51.4.17 void seq64::perform::us_per_quarter_note ( long upqn ) [inline]
12.51.4.18 long seq64::perform::us_per_quarter_note( ) const [inline]
12.51.4.19 const gui_assistant& seq64::perform::gui( ) const [inline]
12.51.4.20 gui_assistant& seq64::perform::gui() [inline]
12.51.4.21 const keys_perform& seq64::perform::keys( ) const [inline]
12.51.4.22 keys_perform& seq64::perform::keys() [inline]
12.51.4.23 mastermidibus& seq64::perform::master_bus() [inline]
12.51.4.24
          void seq64::perform::filter_by_channel( bool flag ) [inline]
12.51.4.25 bool seq64::perform::is_running() const [inline]
12.51.4.26 bool seq64::perform::is_pattern_playing() const [inline]
12.51.4.27 bool seq64::perform::toggle_song_start_mode( ) [inline]
12.51.4.28 void seq64::perform::song_start_mode ( bool flag ) [inline]
12.51.4.29
          bool seq64::perform::song_start_mode( ) const [inline]
12.51.4.30 bool seq64::perform::is_jack_running() const [inline]
12.51.4.31
          bool seq64::perform::is_jack_master( ) const [inline]
12.51.4.32 bool seq64::perform::is_paused() const [inline]
12.51.4.33 bool seq64::perform::is_pausable() const [inline]
12.51.4.34 void seq64::perform::enregister( performcallback * pfcb ) [inline]
```

pfcb Provides the pointer to the performance callback.

12.51.4.35 bool seq64::perform::clear_all ()

The mainwind module calls this function. Note that perform now handles the "is modified" flag on behalf of all external objects, to centralize and simplify the dirtying of a MIDI tune.

Anything else to clear? What about all the other sequence flags? We can beef up delete_sequence() for them, at some point.

Added stazed code from 1.0.5 to abort clearing if any of the sequences are in editing.

Returns

Returns true if the clear-all operation could be performed. If false, then at least one active sequence was in editing mode.

12.51.4.36 void seq64::perform::launch (int ppqn)

This function is called in main(). We collected all the calls here as a simplification, and renamed it because it is more than just initialization. This function must be called after the perform constructor and after the configuration file and command-line configuration overrides.

Parameters

ppqn Provides the PPQN value, which is either the default value (192) or is read from the "user" configuration file.

12.51.4.37 void seq64::perform::new_sequence (int seq)

Then it activates the pattern [this is done in the install_sequence() function]. It doesn't deal with thrown exceptions.

This function is called by the seqmenu and mainwid objects to create a new sequence. We now pass this sequence to install_sequence() to better handle potential memory leakage, and to make sure the sequence gets counted. Also, adding a new sequence from the user-interface is a significant modification, so the "is modified" flag gets set.

Change Note ca 2016-05-15 If enabled, wire in the MIDI buss override.

Parameters

seq The prospective sequence number of the new sequence.

12.51.4.38 void seq64::perform::add_sequence (sequence * seq, int prefnum)

No check is made for a null pointer, but the install_sequence() call will make sure such a pointer is officially logged.

This function checks for the preferred sequence number. This is the number that was specified by the Sequence Number meta-event for the current track. If the preferred sequence number is in the valid range (0 to m_sequence — max) and it is not active, add it and activate it. Otherwise, iterate through all patterns from prefnum to m_ sequence_max and add and activate the first one that is not active, and then finish.

Finally, note that this function is used only by midifile, when reading in a MIDI song. Therefore, the "is modified" flag is *not* set by this function; loading a sequence from a file is not a modification that should lead to a prompt for saving the file later.

Todo Shouldn't we wrap around the sequence list if we can't find an empty sequence slot after prefnum?

Todo This function needs some deeper analysis against the original, in my opinion.

Warning

The logic of the if-statement in this function was such that *prefnum* could be out-of-bounds in the else-clause. We reworked the logic to be airtight. This bug was caught by gcc 4.8.3 on CentOS, but not on gcc 4.9.3 on Debian Sid!

Parameters

seq	The pointer to the pattern/sequence to add.	1
prefnum	The preferred sequence number of the pattern, as explained above. If this value is out-of-range, then it is basically ignored.	

12.51.4.39 void seq64::perform::delete_sequence (int seq)

We now also solidify the deletion by setting the pointer to null after deletion, so it will blow up if accidentally accessed. The final act is to raise the "is modified" flag, since deleting an existing sequence is always a significant modification.

Now, this function obviously sets the "active" flag for the sequence to false. But there are a few other flags that are not modified; shouldn't we also falsify them here?

Parameters

seq	The sequence number of the sequence to be deleted. It is validated.
-----	---

12.51.4.40 bool seq64::perform::is_sequence_in_edit (int seq)

Parameters

seq	Provides the sequence number to be checked.
-----	---

Returns

Returns truen if the sequence's get_editing() call returns true. Otherwise, false is returned, which can also indicate an illegal sequence number.

12.51.4.41 void seq64::perform::clear_sequence_triggers (int seq)

Parameters

seq Provides the desired sequence. The is_active() function validates this value.

12.51.4.42 void seq64::perform::print_triggers () const

12.51.4.43 void seq64::perform::finish() [inline]

A minor simplification for the main() routine, hides the JACK support macro.

12.51.4.44 midipulse seq64::perform::get_tick() const [inline]

12.51.4.45 midipulse seq64::perform::get_jack_tick() const [inline]

12.51.4.46 void seq64::perform::set_jack_tick (midipulse tick) [inline]

Parameters

tick Provides the current JACK tick (pulse) value to set.

12.51.4.47 void seq64::perform::set_left_tick (midipulse tick, bool setstart = true)

We let the caller determine if this setting is a modification. If the left tick is later than the right tick, the right tick is move to one measure past the left tick.

Todo The perform::m_one_measure member is currently hardwired to PPQN * 4.

Parameters

tick	The tick (MIDI pulse) at which to place the left tick. If the left tick is greater than or equal to the right tick, then the right ticked is moved forward by one "measure's length" ($m_ppqn * 4$) past the left tick.
setstart	If true (the default, and long-standing implicit setting), then the starting tick is also set to the left tick.

12.51.4.48 midipulse seq64::perform::get_left_tick()const [inline]

12.51.4.49 void seq64::perform::set_start_tick(midipulse tick) [inline]

Parameters

tick Provides the starting JACK tick (pulse) value to set.

```
12.51.4.50 midipulse seq64::perform::get_start_tick( ) const [inline]
```

12.51.4.51 void seq64::perform::set_right_tick (midipulse tick, bool setstart = true)

This setting is made only if the tick parameter is at or beyond the first measure. We let the caller determine is this setting is a modification.

Parameters

tick	The tick (MIDI pulse) at which to place the right tick. If less than or equal to the left tick setting, then the left tick is backed up by one "measure's worth" (m_ppqn * 4) worth of ticks from the new right tick.
setstart	If true (the default, and long-standing implicit setting), then the starting tick is also set to the left tick, if that got changed.

```
12.51.4.52 midipulse seq64::perform::get_right_tick( ) const [inline]
```

12.51.4.53 double seq64::perform::left_right_size() const [inline]

Returns

Returns the difference between the right and left tick, cast to double.

12.51.4.54 void seq64::perform::move_triggers (bool direction)

Parameters

direction	Specifies the desired direction; false = left, true = right.
-----------	--

12.51.4.55 void seq64::perform::copy_triggers ()

This copies the triggers between the L marker and R marker to the R marker.

12.51.4.56 void seq64::perform::push_trigger_undo (int track = SEQ64_ALL_TRACKS)

Too bad we cannot yet keep track of all the undoes for the sake of properly handling the "is modified" flag.

This function now has a new parameter. Not added to this function is the seemingly redundant undo-push the seq32 code does; is this actually a seq42 thing?

Also, there is still an issue with our undo-handling for a single track. See pop_trigger_undo().

Parameters

track	A new parameter (found in the stazed seq32 code) that allows this function to operate on a single track. A
	parameter value of SEQ64_ALL_TRACKS (-1, the default) implements the original behavior.

```
12.51.4.57 void seq64::perform::pop_trigger_undo()
```

Todo Look at seq32/src/perform.cpp and the perform::push_trigger_undo(track) function, which has a track parameter that has a -1 values the supports all tracks. It requires two new vectors (one for undo, one for redo), two new flags (likewise). We've put this code in place, macroed out.

```
12.51.4.58 void seq64::perform::pop_trigger_redo()

12.51.4.59 bool seq64::perform::have_undo() const [inline]

12.51.4.60 void seq64::perform::set_have_undo(bool undo) [inline]

12.51.4.61 bool seq64::perform::have_redo() const [inline]

12.51.4.62 void seq64::perform::set_have_redo(bool redo) [inline]

12.51.4.63 void seq64::perform::set_have_redo(int seqnum, midipulse tick)
```

Parameters

	seqnum	Indicates the sequence that needs to have its trigger split.
Ī	tick	The MIDI pulse number at which the trigger should be split.

12.51.4.64 midipulse seq64::perform::get_max_trigger()

Returns

Returns the highest trigger value, or zero. It is not clear why this function doesn't return a "no trigger found" value. Is there always at least one trigger, at 0?

```
12.51.4.65 void seq64::perform::collapse() [inline]

12.51.4.66 void seq64::perform::copy() [inline]

12.51.4.67 void seq64::perform::expand() [inline]

12.51.4.68 midi_control & seq64::perform::midi_control_toggle(int seq)
```

Parameters

seq

Provides the index to pass to is_midi_control_valid() to obtain a control value (such as
c_midi_control_bpm_up) to use to retrieve the desired midi_control object. Note that this value is
unsigned simply to make the legality check of the parameter easier.

Returns

Returns the "toggle" value if the sequence is valid, and a reference to sm_mc_dummy otherwise.

12.51.4.69 midi_control & seq64::perform::midi_control_on (int seq)

Parameters

seq	Provides the index to pass to is_midi_control_valid() to obtain a control value (such as
	c_midi_control_bpm_up) to use to retrieve the desired midi_control object.

Returns

Returns the "on" value if the sequence is valid, and a reference to sm_mc_dummy otherwise.

12.51.4.70 midi_control & seq64::perform::midi_control_off (int seq)

Parameters

seq	Provides a control value (such as c_midi_control_bpm_up) to use to retrieve the desired midi_control object.
-----	--

Returns

Returns the "off" value if the sequence is valid, and a reference to sm mc dummy otherwise.

12.51.4.71 void seq64::perform::handle_midi_control (int ctrl, bool state)

Parameters

ctrl	The MIDI control value to use to perform an operation.
state	····· otalio or are comment, accomment and temperature
	values:

```
c_midi_control_mod_replace
c_midi_control_mod_snapshot
c_midi_control_mod_queue
c_midi_control_mod_gmute
c_midi_control_mod_glearn
```

12.51.4.72 const std::string & seq64::perform::get_screen_set_notepad (int *screenset*) const

Parameters

screenset	The ID number of the string set, an index into the m_screen_set_notepad[] array. This value is
	validated.

Returns

Returns a reference to the desired string, or to an empty string if the screen-set number is invalid.

```
12.51.4.73 const std::string& seq64::perform::current_screen_set_notepad( ) const [inline]
```

12.51.4.74 void seq64::perform::set_screen_set_notepad (int screenset, const std::string & notepad)

Parameters

screenset	The ID number of the string set, an index into the m_screen_set_xxx[] arrays.
notepad	Provides the string date to copy into the notepad. Not sure why a pointer is used, instead of nice "const std::string &" parameter. And this pointer isn't checked. Fixed.

12.51.4.75 void seq64::perform::set_screen_set_notepad (const std::string & note) [inline]

Parameters

	note	The string value to set into the notepad text.
--	------	--

```
12.51.4.76 int seq64::perform::get_screenset() const [inline]
```

12.51.4.77 void seq64::perform::set_playing_screenset()

This function is called when one of the snapshot keys is pressed.

For each value up to m_seqs_in_set (32), the index of the current sequence in the current screen set (m_playing _ _screen) is obtained. If the sequence is active and the sequence actually exists, it is processed; null sequences are no longer flagged as an error, they are just ignored.

Modifies m_playing_screen, m_playscreen_offset, stores the current playing-status of each sequence in m_tracks ← _mute_state[], and then calls mute_group_tracks(), turns on unmuted tracks in the current screen-set.

Basically, this function retrieves and saves the playing status of the sequences in the current play-screen, sets the play-screen to the current screen-set, and then mutes the previous play-screen. It is called via the c_midi_control — play_ss value or via the set-playing-screen-set keystroke.

```
12.51.4.78 void seq64::perform::set_screenset ( int ss )
```

It's not clear that we need to set the "is modified" flag just because we changed the screen set, so we don't.

As a new feature, we would like to queue-mute the previous screenset, and queue-unmute the newly-selected screenset. Still working on getting it right.

Parameters

ss The index of the desired new screen set. It is forced to range from 0 to m_max_sets - 1. The clamping seems weird, but hews to seq24. What it does is let the user wrap around the screen-sets in the user interface.

```
12.51.4.79 int seq64::perform::get_playing_screenset() const [inline]
```

12.51.4.80 bool seq64::perform::any_group_unmutes () const

If they're all zero, we don't need to save them.

```
12.51.4.81 void seq64::perform::mute_group_tracks()
```

It loops through every screen-set. In each screen-set, it acts on each active sequence. If the active sequence is in the current "in-view" screen-set (m_screenset as opposed to m_playing_screen), and its m_track_mute_state[] is true, then the sequence is turned on, otherwise it is turned off.

Change Note tdeagan 2015-12-22 via git pull. Replaced m_playing_screen with m_screenset.

Change Note 2016-05-06 It seems to us that the for (i) clause should have i range from 0 to m_max_sets, not m_seqs_in_set. So let's do it, pre-emptively.

```
12.51.4.82 void seq64::perform::select_and_mute_group ( int group )
```

Called in perform and in mainwnd.

Parameters

group Provides the group number for the group to be muted.

```
12.51.4.83 void seq64::perform::set_song_mute( mute_op_t op )
```

The sequence::set_song_mute() and toggle_song_mute() functions do all the work, including mp-dirtying the sequence.

We've modified this function to call mute_all_tracks() and toggle_all_tracks() in order to consolidate the code and (cough cough) fix a bug in this functionality from the mainwind menu.

Parameters

op | Provides the "flag" that indicates if this function is to set mute on, off, or to toggle the mute status.

```
12.51.4.84 void seq64::perform::set_mode_group_mute( ) [inline]
12.51.4.85 void seq64::perform::unset_mode_group_mute( ) [inline]
12.51.4.86 void seq64::perform::select_group_mute( int mutegroup )
```

Then, no matter what, it makes the desired mute-group the selected mute-group. Compare to set_and_copy_

mute_group().

One thing to note is that, once saved, then, if used, it is applied to the current screen-set, even if it is not the screen-set whose playing status were saved.

mutegroup	The number of the desired mute group, clamped to be between 0 and m_seqs_in_set-1.
	Obviously, it is the set whose state is to be stored, if in group-learn mode.

```
12.51.4.87 void seq64::perform::set_mode_group_learn()
```

This function is called via a MIDI control c midi control mod glearn and via the group-learn keystroke.

```
12.51.4.88 void seq64::perform::unset_mode_group_learn()
```

Then unsets the group-learn mode flag. This function is called via a MIDI control c_midi_control_mod_glearn, via the group-learn keystroke, and in mainwnd::on key press event(), to end the group-learn mode.

Shouldn't this function also call this one, to perfectly complement set_mode_group_learn: unset_mode_group_ \leftarrow mute(). Too tricky.

```
12.51.4.89 bool seq64::perform::is_group_learning() [inline]

12.51.4.90 void seq64::perform::set_and_copy_mute_group(int mutegroup)
```

Then the mute-group is stored in m_tracks_mute_state[], which holds states for only the number of sequences in a set

Compare to select_group_mute(); its main difference is that it will at least copy the states even if not in group-learn mode. And, if in group-learn mode, it will grab the playing states of the sequences before copying them.

This function is used only once, in select_and_mute_group(). It used to be called just select_mute_group(), but that's too easy to confuse with select_group_mute().

Change Note tdeagan 2015-12-22 via git pull: git pull https://github.com/TDeagan/sequencer64.

git mute_groups m_screenset replaces m_playscreen_offset.

Parameters

mutaaraun	Provides the mute-group to select.
mutegroup	Provides the mate-group to select.

12.51.4.91 void seq64::perform::start (bool state)

Parameters

state	What does this state mean?

```
12.51.4.92 void seq64::perform::stop ( )
```

The logic seems backward here, in that we call inner_stop() if JACK is not running. Or perhaps we misunderstand the meaning of m_jack_running?

Stazed:

This function's sole purpose was to prevent inner_stop() from being called internally when jack was running...potentially twice. inner_stop() was called by output_func() when jack sent a JackTransportStopped message. If seq42 initiated the stop, then stop_jack() was called which then triggered the JackTransportStopped message to output_func() which then triggered the bool stop_jack to call inner_stop(). The output_func() call to inner_stop() is only necessary when some other jack client sends a jack_transport_stop message to jack, not when it is initiated by seq42. The method of relying on jack to call inner_stop() when internally initiated caused a (very) obscure apparent freeze if you press and hold the start/stop key if set to toggle. This occurs because of the delay between ${\tt JackTransportStarting}$ and ${\tt JackTransportStopped}$ if both triggered in rapid succession by holding the toggle key down. The variable global_is_running gets set false by a delayed inner_stop() from jack after the start (true) is already sent. This means the global is set to true when jack is actually off (false). Any subsequent presses to the toggle key send a stop message because the global is set to true. Because jack is not running, output_func() is not running to send the inner_stop() call which resets the global to false. Thus an apparent freeze as the toggle key endlessly sends a stop, but inner_stop() never gets called to reset. Whoo! So, to fix this we just need to call $inner_stop()$ directly rather than wait for jack to send a delayed stop, only when running. This makes the whole purpose of this stop() function unneeded. The check for m_jack_running is commented out and this function could be removed. It is being left for future generations to ponder!!!

```
12.51.4.93 void seq64::perform::start_jack( ) [inline]

12.51.4.94 void seq64::perform::stop_jack( ) [inline]

12.51.4.95 void seq64::perform::position_jack( bool state )

12.51.4.96 void seq64::perform::off_sequences( )

12.51.4.97 void seq64::perform::all_notes_off( )
```

Then flush the master MIDI buss.

```
12.51.4.98 void seq64::perform::set_active ( int seq, bool active )
```

If setting it active, the sequence::number() setter is called. It won't modify the sequence's internal copy of the sequence number if it has already been set.

Parameters

seq	Provides the prospective sequence number.
active	True if the sequence is to be set to the active state.

12.51.4.99 void seq64::perform::set_was_active (int seq)

Why do we need this routine?

Parameters

seq The pattern number. It is checked for validity.

12.51.4.100 bool seq64::perform::is_dirty_main (int seq)

See the sequence::is_dirty_main() function.

Parameters

seq The pattern number. It is checked for validity.

Returns

Returns the was-active-main flag value, before setting it to false. Returns false if the pattern was invalid.

12.51.4.101 bool seq64::perform::is_dirty_edit (int seq)

Parameters

seq The pattern number. It is checked for validity.

Returns

Returns the was-active-edit flag value, before setting it to false. Returns false if the pattern was invalid.

12.51.4.102 bool seq64::perform::is_dirty_perf (int seq)

Parameters

seq The pattern number. It is checked for validity.

Returns

Returns the was-active-perf flag value, before setting it to false. Returns false if the pattern/sequence number was invalid.

12.51.4.103 bool seq64::perform::is_dirty_names (int seq)

seq The pattern number. It is checked for validity.

Returns

Returns the was-active-names flag value, before setting it to false. Returns false if the pattern/sequence number was invalid.

12.51.4.104 bool seq64::perform::is_active(int seq) const [inline]

Todo We should have the sequence object keep track of its own activity and access that via a reference or pointer.

Parameters

seq

The pattern number. It is checked for invalidity. This can lead to "too many" (i.e. redundant) checks, but we're trying to centralize such checks in this function.

Returns

Returns the value of the active-flag, or false if the sequence was invalid or null.

12.51.4.105 const sequence* seq64::perform::get_sequence(int seq) const [inline]

This is the const version.

Parameters

seq The prospective sequence number.

Returns

Returns the value of m_seqs[seq] if seq is valid. Otherwise, a null pointer is returned.

12.51.4.106 sequence* seq64::perform::get_sequence(int seq) [inline]

Parameters

seq The prospective sequence number.

Returns

Returns the value of m_seqs[seq] if seq is valid. Otherwise, a null pointer is returned.

12.51.4.107 bool seq64::perform::is_exportable (int seq) const

Parameters

seq	The index of the desired sequence.
-----	------------------------------------

Returns

Returns true if the sequence has the three properties noted above.

12.51.4.108 void seq64::perform::reset_sequences (bool pause = false)

Note that these calls are folded into one member function of the sequence class. Finally, flush the master MIDI buss.

Parameters

pause	Try to prevent notes from lingering on pause if true.
-------	---

12.51.4.109 void seq64::perform::play (midipulse tick)

Starts the playing of all the patterns/sequences.

This function just runs down the list of sequences and has them dump their events. It skips sequences that have no playable MIDI events.

Note how often the "s" (sequence) pointer is used. Is it worth offloading all these calls to a new sequence function?

Parameters

tick	ne tick at which to start playing	
tick	ne tick at which to star	t playing.

12.51.4.110 void seq64::perform::set_orig_ticks (midipulse tick)

This is really the "last tick" value, so we renamed sequence::set_orig_tick() to sequence::set_last_tick().

Parameters

tick Provides the last-tick value to be set for each sequence that is active.

12.51.4.111 void seq64::perform::set_beats_per_minute (int bpm)

Replaces perform::set_bpm() from seq24.

The value is set only if neither JACK nor this performance object are running.

It's not clear that we need to set the "is modified" flag just because we changed the beats per minute. This setting does get saved to the MIDI file, with the c_bpmtag.

Parameters

bpm	Provides the beats/minute value to be set. It is clamped, if necessary, between the values
	SEQ64_MINIMUM_BPM to SEQ64_MAXIMUM_BPM. They provide a wide range of speeds, well
	beyond what normal music needs.

12.51.4.112 int seq64::perform::get_beats_per_minute() [inline]

Returns

Returns the value of beats/minute from the master buss.

12.51.4.113 void seq64::perform::set_looping (bool looping) [inline]

Parameters

	looping	The boolean value to set for looping, used in the performance editor.
--	---------	---

12.51.4.114 void seq64::perform::set_sequence_control_status (int status)

Then the given status is OR'd into the m_control_status.

Parameters

status The status to	be used.
----------------------	----------

12.51.4.115 void seq64::perform::unset_sequence_control_status (int status)

Then the given status is reversed in m_control_status.

Parameters

status	The status to be used.
--------	------------------------

12.51.4.116 void seq64::perform::sequence_playing_toggle (int seq)

If the m_control_status is c_status_queue, then the sequence's toggle_queued() function is called. Otherwise, if it is c_status_replace, then the status is unset, and all sequences (?) are turned off. Then the sequence's toggle-playing() function is called.

seq The sequence number of the sequence to be potentially toggled

12.51.4.117 void seq64::perform::sequence_playing_change (int seq, bool on)

Used for the implementation of sequence_playing_on() and sequence_playing_off().

Parameters

seq	The number of the sequence to be turned off.
on	True if the sequence is to be turned on, false if it is to be turned off.

12.51.4.118 void seq64::perform::sequence_playing_on(int seq) [inline]

Parameters

12.51.4.119 void seq64::perform::sequence_playing_off(int seq) [inline]

Parameters

12.51.4.120 void seq64::perform::mute_all_tracks (bool flag = true)

Covers tracks from 0 to m_sequence_max.

We have to also set the sequence's playing status, in opposition to the mute status, in order to see the sequence status change on the user-interface. HMMMMMM.

Parameters

flag	If true (the default), the song-mute of the sequence is turned on. Otherwise, it is turned off.
------	---

12.51.4.121 void seq64::perform::toggle_all_tracks ()

Covers tracks from 0 to m_sequence_max.

12.51.4.122 void seq64::perform::mute_screenset (int ss, bool flag = true)

ss	The screen-set to be operated upon.
flag	If true (the default), the song-mute of the sequence is turned on. Otherwise, it is turned off.

12.51.4.123 void seq64::perform::output_func ()

This function is called by the free function output_thread_func(). Here's how it works:

```
    It runs while m_outputing is true.
    MORE TO COME. Yeah, a lot more to come. It is a complex function.
```

Change Note ca 2016-01-26 Hurray, seq24 is coming back to life! We see that there is a fix for clock tick drift here, which relies on using long and long long values. See the Changelog for seq24 0.9.3.

- 1. Get delta time (current last).
- 2. Get delta ticks from time.
- 3. Add to current ticks.
- 4. Compute prebuffer ticks.
- 5. Play from current tick to prebuffer.

Figure out how much time we need to sleep, and do it.

Now we want to trigger every c_thread_trigger_width_us, and it took us delta_us to play(). Also known as the "sleeping_us".

Check MIDI clock adjustment. Note that we replaced "60000000.0f / m_ppqn / bpm" with a call to a function. We also removed the "f" specification from the constants.

```
12.51.4.124 void seq64::perform::input_func()

12.51.4.125 void seq64::perform::set_group_mute_state(int gtrack, bool muted) [inline]
```

The index value is the track number offset by the number of the selected mute group (which is equivalent to a set number) times the number of sequences in a set. This function is used in midifile and optionsfile when parsing the file to get the initial mute-groups.

Parameters

gtrack	The number of the track to be muted/unmuted.
muted	This boolean indicates the state to which the track should be set.

12.51.4.126 bool seq64::perform::get_group_mute_state(int gtrack) [inline]

Uses the mute_group_offset() function. This function is used in midifile and optionsfile when writing the file to get the initial mute-groups.

gtrack The number of the track for which the state is to be obtained. Like set_group_mute_state(), this value is offset by adding m mute group selected * m seqs in set.

Returns

Returns the desired m_mute_group[] value.

```
12.51.4.127 void seq64::perform::set_offset(int offset) [inline]

Sets m_offset = offset * c_mainwnd_rows * c_mainwnd_cols.

Parameters

offset | The desired offset.
```

```
12.51.4.128 int seq64::perform::get_offset( ) const [inline]
```

Inactive patterns get the value set to false. Used in unsetting the snapshot status (c_status_snapshot).

```
12.51.4.130 void seq64::perform::restore_playing_state()
```

12.51.4.129 void seq64::perform::save_playing_state ()

Used in unsetting the snapshot status (c_status_snapshot).

```
12.51.4.131 std::string seq64::perform::key_name ( unsigned int k ) const [inline]
```

Parameters

k The key number for which to return the string name of the key.

```
12.51.4.132 keys_perform::SlotMap& seq64::perform::get_key_events() [inline]

12.51.4.133 keys_perform::SlotMap& seq64::perform::get_key_groups() [inline]

12.51.4.134 keys_perform::RevSlotMap& seq64::perform::get_key_events_rev() [inline]

12.51.4.135 keys_perform::RevSlotMap& seq64::perform::get_key_groups_rev() [inline]

12.51.4.136 bool seq64::perform::show_ui_sequence_key() const [inline]
```

Used in mainwid, options, optionsfile, userfile, and perform.

12.51.4.137 void seq64::perform::show_ui_sequence_key(bool flag) [inline]

Parameters

flag | Provides the flag to set into keys().show_ui_sequence_key().

12.51.4.138 bool seq64::perform::show_ui_sequence_number() const [inline]

Used in mainwid, optionsfile, and perform.

12.51.4.139 void seq64::perform::show_ui_sequence_number(bool flag) [inline]

Parameters

flag | Provides the value to set into keys().show_ui_sequence_number().

12.51.4.140 unsigned int seq64::perform::lookup_keyevent_key (int seqnum)

If we're not in legacy mode, then we adjust for the screenset, so that screensets greater than 0 can also show the correct key name, instead of a question mark.

Legacy seq24 already responds to the toggling of the mute state via the shortcut keys even if screenset > 0, but it shows the question mark.

Parameters

seqnum The number of the sequence for which to return the event key.

Returns

Returns the desired key. If there is no such value, then the period ('?') character is returned.

12.51.4.141 long seq64::perform::lookup_keyevent_seq (unsigned int keycode) [inline]

The inverse of lookup_keyevent_key().

Parameters

keycode The number of the event key for which to return the configured sequence number.

Returns

Returns the desired sequence. If there is no such value, then a sequence number of 0 is returned.

12.51.4.142 unsigned int seq64::perform::lookup_keygroup_key(long groupnum) [inline]

Parameters

groupnum The number of the sequence for which to return the group key.
--

Returns

Returns the desired key. If there is no such value, then the period ('.') character is returned.

12.51.4.143 long seq64::perform::lookup_keygroup_group (unsigned int keycode) [inline]

The inverse of lookup_keygroup_key().

Parameters

	keycode	The number of the group key for which to return the configured sequence number.
--	---------	---

Returns

Returns the desired group number. If there is no such value, then a group number of 0 is returned.

```
12.51.4.144 void seq64::perform::start_playing ( bool songmode = false )
```

We've reversed the start() and start_jack() calls so that JACK is started first, to match all of the other use-cases for playing that we've found in the code. Note that the complementary function, stop_playing(), is an inline function defined in the header file.

Note

It would be nice to know why the following code snippet disables the mute/unmute functionality of the performance/song editor:

```
position_jack(false);
start_jack();
start(false);

The jack_assistant::position() function doesn't use the boolean
parameter at present; that code is effectively disabled. Okay, now it
does, if the "relocate" parameter is true. See
perform::position_jack() and jack_assistant::position(). This
parameter, when true, allows the "klick" application to get proper
position data.

The perform::start() function passes its boolean flag to
perform::inner_start(), which sets the playback mode to that flag; if
that flag is false, that turns off "song" mode. So that explains why
mute/unmute is disabled.
```

Parameters

songmode	Indicates if the caller wants to start the playback in JACK mode. In the seq42 (yes, "42", not "24") code at GitHub, this flag was identical to the "global_jack_start_mode" flag, which is true for Song
	mode, and false for Live mode. False disables Song mode, and is the default, which matches seq24. If the previous state was "paused", then we start it in Live mode, which works because Song mode has already turned on the sequences. This method is not quite intuitive, because it is
	really following Live mode.

12.51.4.145 void seq64::perform::pause_playing ()

Currently almost the same as stop_playing(), but expanded as noted in the comments so that we ultimately have more granular control over what happens. We're researching the whole sequence of stopping and starting, and it can be tricky to make correct changes.

We still need to make restarting pick up at the same place in ALSA mode; in JACK mode, JACK transport takes care of that feature.

12.51.4.146 void seq64::perform::stop_playing ()

Stops playback, turns off the (new) m_is_paused flag, and set the "is-pattern-playing" flag to false. With stop, reset the start-tick to either the left-tick or the 0th tick (to be determined, currently resets to 0)..

12.51.4.147 void seq64::perform::start_key (bool songmode = false)

Meant to be used by GUIs to unify the treatment of keys versus buttons.

Parameters

songmode	The live/play mode parameter to be passed along to the key processor. Defaults to false (live mode).

12.51.4.148 void seq64::perform::pause_key (bool songmode = false)

Meant to be used by GUIs to unify the treatment of keys versus buttons.

Parameters

songmode	The live/play mode parameter to be passed along to the key processor, when starting playback.	
	Defaults to false (live mode).	

12.51.4.149 void seq64::perform::stop_key()

Meant to be used by GUIs to unify the treatment of keys versus buttons.

```
12.51.4.150 void seq64::perform::learn_toggle() [inline]

12.51.4.151 int seq64::perform::decrement_beats_per_minute() [inline]

Actually does a lot of work in those function calls.

12.51.4.152 int seq64::perform::increment_beats_per_minute() [inline]
```

Actually does a lot of work in those function calls.

```
12.51.4.153 int seq64::perform::decrement_screenset( ) [inline]

12.51.4.154 int seq64::perform::increment_screenset( ) [inline]

12.51.4.155 bool seq64::perform::highlight( const sequence & seq ) const [inline]
```

This setting is currently a build-time option, but could be made a run-time option later.

Parameters

seq Provides a reference to the desired sequence.

12.51.4.156 bool seq64::perform::is_smf_0 (const sequence & seq) const [inline]

Parameters

seq Provides a reference to the desired sequence.

12.51.4.157 void seq64::perform::sequence_key (int seq)

This function is use in mainwnd when toggling the mute/unmute setting using keyboard keys.

Parameters

seq The sequence's control-key number, which is relative to the current screen-set.

12.51.4.158 std::string seq64::perform::sequence_label (const sequence & seq)

This string goes on the bottom-left of those user-interface elements.

The format of this string is something like the following example, depending on the "show sequence numbers" option. The values shown are, in this order, sequence number (if allowed), buss number, channel number, beats per bar, and beat width.

No sequence number: 31-16 4/4 Sequence number: 9 31-16 4/4

The sequence number and buss number are re 0, while the channel number is displayed re 1, unless it is an SMF 0 null channel (0xFF), in which case it is 0.

Note

Later, we could add the sequence hot-key to this string, though showing that is not much use in perfnames. Also, this function is a stilted mix of direct access and access through sequence number.

Parameters

seq	Provides the reference to the sequence, use for getting the sequence parameters to be written to the
	label string.

Returns

Returns the filled in label if the sequence is active. Otherwise, an empty string is returned.

12.51.4.159 void seq64::perform::set_input_bus (int bus, bool active)

This function is called by options::input_callback().

Tricky Code See the bus parameter. We should provide two separate functions for this feature, but it is already combined into one input-callback function with a lot of other functionality in the options module.

Parameters

bus	If this value is greater than SEQ64_DEFAULT_BUSS_MAX (32), then it is treated as a user-interface flag (PERFORM_KEY_LABELS_ON_SEQUENCE) that causes all the sequences to be dirtied, and thus get redrawn with the new user-interface setting.
active	Indicates whether the buss or the user-interface feature is active or inactive.

12.51.4.160 bool seq64::perform::mainwnd_key_event (const keystroke & k)

This function handles the keys for the functions of replace, queue, keep-queue, snapshots, toggling mute groups, group learn, and playing screenset. For further keystroke processing, see mainwind :: on_key_press_event().

Keys not handled here are handled in mainwnd: bpm up & down; screenset up & down.

Parameters

k The keystroke object to be handled.

Returns

Returns true if the key was handled.

12.51.4.161 bool seq64::perform::perfroll_key_event (const keystroke & k, int drop_sequence)

It handles the Ctrl keys for cut, copy, paste, and undo.

The "is modified" flag is raised if something is deleted, but we cannot yet handle the case where we undo all the changes. So, for now, we play it safe with the user, even if the user gets annoyed because he knows that he undid all the changes.

Parameters

k	The keystroke object to be handled.
drop_sequence	Provides the index of the sequence whose selected trigger is to be cut, copied, or pasted. (Undo not yet supported).

Returns

Returns true if the key was handled.

12.51.4.162 bool seq64::perform::playback_key_event (const keystroke & k, bool songmode = false)

To be used in mainwnd, perfedit, and seqroll.

The start/end key may be the same key (e.g. Space) to allow toggling when the same key is mapped to both triggers.

Checking is_running() may not work completely in JACK.

Parameters

k Provides the encapsulated keystroke to check.	
songmode	Provides the "jack flag" needed by the mainwind, seqroll, and perfedit windows. Defaults to false, which disables Song mode, and enables Live mode. But using Song mode seems to make the pause key not work in the performance editor.

Returns

Returns true if the keystroke matched the start, stop, or (new) pause keystrokes. Generally, no further keystroke processing is needed in this case.

12.51.4.163 int seq64::perform::max_active_set() const [private]

Returns

Returns the value of the highest active set. A value of 0 represents the first set. If no sequences are active, then -1 is returned.

```
12.51.4.164 void seq64::perform::launch_input_thread( ) [private]
```

This might be a good candidate for a small thread class derived from a small base class.

```
12.51.4.165 void seq64::perform::launch_output_thread( ) [private]
```

This might be a good candidate for a small thread class derived from a small base class.

```
12.51.4.166 bool seq64::perform::init_jack( ) [inline], [private]
```

Who calls this routine? The main() routine of the application [via launch()], and the options module, when the Connect button is pressed.

Returns

Returns the result of the init() call; true if JACK sync is now running. If JACK support is not built into the application, then this function returns false, to indicate that JACK is (definitely) not running.

```
12.51.4.167 bool seq64::perform::deinit_jack( ) [inline], [private]
```

Called by launch() and in the options module, when the Disconnect button is pressed.

Returns

Returns the result of the init() call; false if JACK sync is now no longer running. If JACK support is not built into the application, then this function returns true, to indicate that JACK is (definitely) not running.

```
12.51.4.168 bool seq64::perform::seq_in_playing_screen ( int seq ) [private]
```

Parameters

seq	Provides the index of the desired sequence.
-----	---

Returns

Returns true if the sequence adheres to the conditions noted above.

```
12.51.4.169 void seq64::perform::is_modified ( bool flag ) [inline], [private]
```

Parameters

flag The value of the modified flag to be set.

12.51.4.170 bool seq64::perform::is_midi_control_valid (int seq) const [inline], [private]

Parameters

seq	The value that should be in the c_midi_controls range.
-----	--

Returns

Returns true if the parameter is valid. For this function, no error print-out is generated.

12.51.4.171 bool seq64::perform::is_screenset_valid (int screenset) const [inline], [private]

Parameters

screenset	The prospective screenset value.
-----------	----------------------------------

Returns

Returns true if the parameter is valid. For this function, no error print-out is generated.

12.51.4.172 void seq64::perform::set_running(bool running) [inline], [private]

Parameters

lag to be set.	unning The value of the runnin
----------------	--------------------------------

12.51.4.173 void seq64::perform::is_pattern_playing (bool flag) [inline], [private]

12.51.4.174 void seq64::perform::set_playback_mode(bool playbackmode) [inline], [private]

Parameters

playbackmode	The value of the playback mode flag to be set.
--------------	--

12.51.4.175 int seq64::perform::mute_group_offset(int track) [inline], [private]

Parameters

track The number of the desired trace	k.
---------------------------------------	----

12.51.4.176 bool seq64::perform::is_seq_valid (int seq) const [private]

Also see the function is_mseq_valid(), which also checks the pointer stored in the m_seq[] array.

We considered checking the *seq* param against sequence_count(), but this function is called while creating sequences that add to that count, so we continue checking against the "container" size. Also, it is possible to have holes in the array representing inactive sequences, so that sequencer_count() would be too limiting.

Parameters

seq	The sequencer number, in interval [0, m_sequence_max).
-----	--

Returns

Returns true if the sequence number is valid.

12.51.4.177 bool seq64::perform::is_mseq_valid (int seq) const [private]

It also evaluates the m_seq[seq] pointer value.

Note

Since we can have holes in the sequence array, where there are inactive sequences, we check if the sequence is even active before emitting a message about a null pointer for the sequence. We only want to see messages that indicate actual problems.

Parameters

seq Provides the sequence number to be checked. It is checked for validity. We cannot compare the sequence number versus the sequence_count(), because the current implementation can have inactive holes (with null pointers) interspersed with active pointers.

Returns

Returns true if the sequence number is valid as per is seq valid(), and the sequence pointer is not null.

12.51.4.178 bool seq64::perform::install_sequence(sequence * seq, int seqnum) [private]

It is common code and using it prevents inconsistences. It assumes values have already been checked. It does not set the "is modified" flag, since adding a sequence by loading a MIDI file should not set it. Compare new_\circ sequence(), used by mainwid and seqmenu, with add_sequence(), used by midifile.

Parameters

seq	The pointer to the pattern/sequence to add.	
segnum The sequence number of the pattern to be added. Not validated, to save some til		

Returns

Returns true if a sequence was removed, or the sequence was successfully added. In other words, if a real change in sequence pointers occurred. It is up to the caller to decide if the change warrants setting the "is modified" flag.

```
12.51.4.179 void seq64::perform::inner_start ( bool state ) [private]
```

Then, if not is_running(), the playback mode is set to the given state. If that state is true, call off_sequences(). Set the running status, and signal the condition. Then unlock.

Minor issue:

```
In ALSA mode, restarting the sequence moves the progress bar to the beginning of the sequence, even if just pausing. This is fixed by compiling with SEQ64_PAUSE_SUPPORT, which disables calling off_sequences() when starting playback from the song editor / performance window. WE STILL HAVE TO EVALUATE WHAT SIDE-EFFECTS MIGHT OCCUR. ALSO CONSIDER A RUN-TIME --pause-support option for this feature.
```

Parameters

state Sets the playback mode, and, if true, turns off all of the sequences.

```
12.51.4.180 void seq64::perform::inner_stop ( bool midiclock = false ) [private]
```

Note that we do need to set the running flag to false here, even when JACK is running. Otherwise, JACK starts ping-ponging back and forth between positions under some circumstances.

However, if JACK is running, we do not want to reset the sequences... this causes the progress bar for each sequence to remove to near the end of the sequence.

```
12.51.4.181 int seq64::perform::clamp_track( int track ) const [private]
```

Fixed the bug we found, where we checked for track > m segs in set, instead of using the >= operator.

Parameters

track	The track value to be checked and rectified as necessary.
-------	---

Returns

Returns the track parameter, clamped between 0 and m_seqs_in_set-1, inclusive.

```
12.51.4.182 void seq64::perform::set_all_key_events( ) [inline],[private]
12.51.4.183 void seq64::perform::set_all_key_groups( ) [inline],[private]
12.51.4.184 void seq64::perform::set_key_event( unsigned int keycode, long sequence_slot ) [inline],[private]
```

It is called 32 times, corresponding to the pattern/sequence slots in the Patterns window. It first removes the given key-code from the regular and reverse slot-maps. Then it removes the sequence-slot from the regular and reverse slot-maps. Finally, it adds the sequence-slot with a key value of key-code, and adds the key-code with a value of sequence-slot.

Parameters

keycode	The keycode for which to set the sequence slot.
sequence_slot	The sequence slot to be set.

12.51.4.185 void seq64::perform::set_key_group (unsigned int keycode, long group_slot) [inline], [private]

It is called 32 times, corresponding the pattern/sequence slots in the Patterns window. Compare it to the set_key← events() function.

Parameters

keycode	The keycode for which to set the group slot.
group_slot The group slot to be set.	

12.51.5 Friends And Related Function Documentation

12.51.5.1 friend class jack_assistant [friend]

12.51.5.2 friend class keybindentry [friend]

12.51.5.3 friend class midifile [friend]

12.51.5.4 friend class optionsfile [friend]

12.51.5.5 friend class options [friend]

12.51.5.6 int jack_sync_callback (jack_transport_state_t state, jack_position_t * pos, void * arg) [friend]

This JACK synchronization callback informs the specified perform object of the current state and parameters of JACK.

The transport state will be:

- JackTransportStopped when a new position is requested.
- JackTransportStarting when the transport is waiting to start.
- JackTransportRolling when the timeout has expired, and the position is now a moving target.

This is the slow-sync callback, which stazed replaces with jack_process_callback().

Parameters

state	The JACK Transport state.	
pos	The JACK position value.	
arg	The pointer to the jack_assistant object. Currently not checked for nullity, nor dynamic-casted.	

Returns

Returns 1 if the function works, and 0 if something was wrong.

12.51.6 Field Documentation

```
12.51.6.1 midi control seq64::perform::sm_mc_dummy [static],[private]
```

Instantiate the dummy midi control object, which is used in lieu of a null pointer.

static perform & sm_self; Provides a dummy, inactive midi_control object to handle out-of-range midi_control indicies.

We're taking code that basically works already, in the sense that it never seems to access a null pointer. So we're not even risking data transfers between this dummy object and the ones we really want to use.

```
12.51.6.2 bool seq64::perform::m_song_start_mode [private]

12.51.6.3 gui_assistant& seq64::perform::m_gui_support [private]

12.51.6.4 bool seq64::perform::m_mute_group[c_gmute_tracks] [private]
```

This value determines whether a particular track will be muted or unmuted, and it can handle all tracks available in the application (currently 1024). Note that the current state of playing can be "learned", and stored herein as the desired state for the track.

```
12.51.6.5 bool seq64::perform::m_tracks_mute_state[c_seqs_in_set] [private]
```

Unlike the m_mute_group[] array, this holds the current state, rather than the state desired by activating a mute group, and it applies to only one screen-set.

```
12.51.6.6 bool seq64::perform::m_mode_group [private]
```

This value starts out true. It is altered by the c_midi_control_mod_gmute handler or when the keys().group_off() or the keys().group_on() keys are struck.

```
12.51.6.7 bool seq64::perform::m_mode_group_learn [private]
12.51.6.8 int seq64::perform::m mute group selected [private]
```

It seems like a "group" is essentially a "set" that is selected for the saving and restoring of the status of all patterns in that set.

```
12.51.6.9 int seq64::perform::m_playing_screen [private]
```

In seq24, this value is altered by set_playing_screenset(), which is called by handle_midi_control(c_midi_control ← _play_ss, state).

```
12.51.6.10 int seq64::perform::m_playscreen_offset [private]
```

Saves some multiplications, should make the code easier to grok, and centralizes the use of c_seqs_in_set, which we want to be able to change at run-time, as a future enhancement.

```
12.51.6.11 sequence* seq64::perform::m_seqs[c_max_sequence] [private]
```

Todo First, make the sequence array a vector, and second, put allof these flags into a structure and access those members indirectly.

```
12.51.6.12 bool seq64::perform::m_seqs_active[c_max_sequence] [private]
```

This array can have "holes" with inactive sequences, so every sequence needs to be checked before using it.

```
12.51.6.13 bool seq64::perform::m_was_active_main[c_max_sequence] [private]
```

This value seems to be used only in maintaining dirtiness-status; did some process modify the sequence? Was it's mute/unmute status changed?

```
12.51.6.14 bool seq64::perform::m_was_active_edit[c_max_sequence] [private]
```

This value seems to be used only in maintaining dirtiness-status for editing the mute/unmute status during pattern editing.

```
12.51.6.15 bool seq64::perform::m_was_active_perf[c_max_sequence] [private]
```

This value seems to be used only in maintaining dirtiness-status for editing the mute/unmute status during performance/song editing.

```
12.51.6.16 bool seq64::perform::m_was_active_names[c_max_sequence] [private]
```

This value seems to be used only in maintaining dirtiness-status for editing the mute/unmute status during performance names editing. Not sure that it serves a real purpose; perhaps created with an eye to editing the pattern name in the song editor?

```
12.51.6.17 bool seq64::perform::m_sequence_state[c_max_sequence] [private]
```

12.51.6.18 mastermidibus seq64::perform::m_master_bus [private]

12.51.6.19 pthread_t seq64::perform::m_out_thread [private]

Provides a "handle" to the output thread.

```
12.51.6.20 pthread_t seq64::perform::m_in_thread [private]
12.51.6.21 bool seq64::perform::m_out_thread_launched [private]
12.51.6.22 bool seq64::perform::m_in_thread_launched [private]
12.51.6.23 bool seq64::perform::m_running [private]
However, this flag is conflated with some JACK support, and we have to supplement it with another flag, m_←
pattern_playing.
12.51.6.24 bool seq64::perform::m_is_pattern_playing [private]
It replaces rc_settings :: is_pattern_playing(), which is gone, since the perform object is now visible to all classes
that care about it.
12.51.6.25 bool seq64::perform::m_inputing [private]
12.51.6.26 bool seq64::perform::m_outputing [private]
12.51.6.27 bool seq64::perform::m_looping [private]
If true, the performance will loop between the L and R markers in the performance editor.
12.51.6.28 bool seq64::perform::m_playback_mode [private]
There are two, "live" and "song", indicated by the following values:
        m_playback_mode == true:
                                          playback/song mode
12.51.6.29 int seq64::perform::m_ppqn [private]
12.51.6.30 int seq64::perform::m_beats_per_bar [private]
The default value is SEQ64_DEFAULT_BEATS_PER_MEASURE (4).
12.51.6.31 int seq64::perform::m_beat_width [private]
```

The default value is SEQ64_DEFAULT_BEAT_WIDTH (4).

```
12.51.6.32 int seq64::perform::m_clocks_per_metronome [private]
```

This value provides the number of MIDI clocks between metronome clicks. The default value of this item is 24. It can also be read from some SMF 1 files, such as our hymne.mid example.

```
12.51.6.33 int seq64::perform::m_32nds_per_quarter [private]
```

Useful in export. A duplicate of the same member in the sequence class.

```
12.51.6.34 long seq64::perform::m_us_per_quarter_note [private]
```

Useful in export. A duplicate of the same member in the sequence class.

```
12.51.6.35 midipulse seq64::perform::m_one_measure [private]
```

We can save some multiplications, and, more importantly, later define a more flexible definition of "one measure's worth" than simply four quarter notes.

```
12.51.6.36 midipulse seq64::perform::m_left_tick [private]
```

Note that "tick" is actually "pulses".

```
12.51.6.37 midipulse seq64::perform::m_right_tick [private]
```

Note that "tick" is actually "pulses".

```
12.51.6.38 midipulse seq64::perform::m_starting_tick [private]
```

By default, this value is always reset to the value of the "left tick". We want to eventually be able to leave it at the last playing tick, to support a "pause" functionality. Note that "tick" is actually "pulses".

```
12.51.6.39 midipulse seq64::perform::m_tick [mutable], [private]
```

The m_tick member holds the tick to be used in displaying the progress bars and the maintime pill. It is mutable because sometimes we want to adjust it in a const function for pause functionality.

```
12.51.6.40 midipulse seq64::perform::m_jack_tick [private]

12.51.6.41 bool seq64::perform::m_usemidiclock [private]

12.51.6.42 bool seq64::perform::m_midiclockrunning [private]

12.51.6.43 int seq64::perform::m_midiclocktick [private]

12.51.6.44 int seq64::perform::m_midiclockpos [private]

12.51.6.45 bool seq64::perform::m_is_paused [private]

12.51.6.46 std::string seq64::perform::m_screen_set_notepad[c_max_sets] [private]

12.51.6.47 midi_control seq64::perform::m_midi_cc_toggle[c_midi_controls] [private]

12.51.6.48 midi_control seq64::perform::m_midi_cc_on[c_midi_controls] [private]

12.51.6.49 midi_control seq64::perform::m_midi_cc_off[c_midi_controls] [private]

12.51.6.50 int seq64::perform::m_offset [private]
```

It is used in the MIDI control of the playback status of the sequences in the current screen-set. It is also used to offset the sequence numbers so that the control (mute/unmute) keys can be shown on any screen-set.

```
12.51.6.51 int seq64::perform::m_control_status [private]
```

Need to learn more about this one. It is used in the replace, snapshot, and queue functionality.

```
12.51.6.52 int seq64::perform::m_screenset [private]
```

This is merely the screen-set that is in view. The fix of tdeagan substitutes the "in-view" screen-set for the "playing" screen-set.

```
12.51.6.53 int seq64::perform::m_seqs_in_set [private]
```

This change will require some arrays to be dynamically allocated (vectors).

```
12.51.6.54 int seq64::perform::m_max_sets [private]
```

Again, currently set to the old value, which is used in hard-wired array sizes. To make it variable will require a move from arrays to vectors.

```
12.51.6.55 int seq64::perform::m_sequence_count [private]
```

Used by the install_sequence() function. Note that this value is not a suitable replacement for c_max_sequence/m← _sequence_max, because there can be inactive sequences amidst the active sequences.

```
12.51.6.56 int seq64::perform::m_sequence_max [private]
```

However, this value is already 32 * 32 = 1024, and is probably enough for any usage. Famous last words?

```
12.51.6.57 int seq64::perform::m_edit_sequence [private]
```

Moving this status from seqmenu into perform for better centralized management.

```
12.51.6.58 bool seq64::perform::m_is_modified [private]
```

All the GUIs seem to use a perform object.

```
12.51.6.59 condition_var seq64::perform::m_condition_var [private]
```

It is signalled if playback has been started. The output thread function waits on this variable until m_running and m_outputing are false. This variable is also signalled in the perform destructor.

```
12.51.6.60 jack_assistant seq64::perform::m_jack_asst [private]

12.51.6.61 bool seq64::perform::m_have_undo [private]

12.51.6.62 std::vector<int> seq64::perform::m_undo_vect [private]

12.51.6.63 bool seq64::perform::m_have_redo [private]


12.51.6.64 std::vector<int> seq64::perform::m_redo_vect [private]

12.51.6.65 std::vector<performcallback *> seq64::perform::m_notify [private]
```

12.52 seq64::performcallback Struct Reference

Provides for notification of events.

Inheritance diagram for seq64::performcallback:



Public Member Functions

virtual void on_grouplearnchange (bool)
 A do-nothing callback.


12.52.1 Detailed Description

Provide a response to a group-learn change event.

12.52.2	Member Function Documentation
12 52 2 1	<pre>virtual void seq64::performcallback::on_grouplearnchange(bool) [inline], [virtual]</pre>
12.02.2.1	vintair void sequeperiorinicalisatessin_groupicalitoriange (sect) [Infiline], [VIII atal]
"state" is	an Unused parameter.
Reimpler	nented in seq64::mainwnd.
12.53	seq64::perfroll Class Reference

This class implements the performance roll user interface.

Inheritance diagram for seq64::perfroll:



Public Member Functions

• perfroll (perform &perf, perfedit &parent, Gtk::Adjustment &hadjust, Gtk::Adjustment &vadjust, int ppqn=S← EQ64_USE_DEFAULT_PPQN)

Principal constructor.

virtual ∼perfroll ()

This destructor deletes the interaction object.

void set_guides (int snap, int measure, int beat)

This function sets the m_snap, m_measure_length, and m_beat_length members directly from the function parameters, which are in units of pulses (sometimes misleadingly called "ticks".)

· void update sizes ()

Updates the sizes of various items.

void init_before_show ()

Sets the roll-lengths ticks member.

void fill_background_pixmap ()

This function updates the background of the piano roll.

• void increment_size ()

Increments the value of m_roll_length_ticks by the PPQN * 512, then calls update_sizes().

• void draw all ()

Provides a very common sequence of calls used in perfroll_input.

- void follow progress ()
- void redraw progress ()

Helper function to simplify the client call.

Private Member Functions

void draw progress ()

Draws the progress line that shows where we are in the performance.

void redraw dirty sequences ()

Redraws patterns/sequences that have been modified.

void set_ppqn (int ppqn)

Handles changes to the PPQN value in one place.

void convert_xy (int x, int y, midipulse &ticks, int &seq)

Converts (x, y) coordinates on the piano roll to tick (pulse) and sequence numbers.

void convert_x (int x, midipulse &ticks)

Converts a tick-offset on the x coordinate.

void snap_x (int &x)

This function performs a 'snap' action on x.

void draw_sequence_on (int seqnum)

Draws the given pattern/sequence on the given drawable area.

void draw_background_on (int seqnum)

Draws the given pattern/sequence background on the given drawable area.

void draw_drawable_row (long y)

Not quite sure what this draws yet.

• void change_horz ()

Changes the 4-bar horizontal offset member and queues up a draw operation.

· void change_vert ()

Changes the 4-bar vertical offset member and queues up a draw operation.

void split_trigger (int sequence, midipulse tick)

Splits a trigger, whatever that means.

• void enqueue draw ()

Wraps queue_draw() and forwards the call to the parent perfedit, so that it can forward it to any other perfedit that exists

void set_zoom (int z)

Implements the horizontal zoom feature.

· void horizontal adjust (double step)

This function provides optimization for the on_scroll_event() function.

void vertical_adjust (double step)

This function provides optimization for the on_scroll_event() function.

• void horizontal set (double value)

Sets the exact position of a horizontal scroll-bar.

void vertical_set (double value)

Sets the exact position of a vertical scroll-bar.

• void on_realize ()

Provides the on-realization callback.

bool on_expose_event (GdkEventExpose *ev)

Handles the on-expose event.

• bool on_button_press_event (GdkEventButton *ev)

This callback function handles a button press by forwarding it to the interaction object's button-press function.

bool on_button_release_event (GdkEventButton *ev)

This callback function handles a button release by forwarding it to the interaction object's button-release function.

bool on motion notify event (GdkEventMotion *ev)

Handles motion notification by forwarding it to the interaction object's motion-notification callback function.

bool on_scroll_event (GdkEventScroll *ev)

Handles horizontal and vertical scrolling.

bool on_focus_in_event (GdkEventFocus *ev)

This callback handles an in-focus event by setting the flag to HAS_FOCUS.

bool on_focus_out_event (GdkEventFocus *ev)

This callback handles an out-of-focus event by resetting the flag HAS_FOCUS.

void on_size_allocate (Gtk::Allocation &al)

Upon a size allocation event, this callback calls the base-class version of this function, then sets m_window_x and m_window_y, and calls update_sizes().

• bool on_key_press_event (GdkEventKey *ev)

This callback function handles a key-press event.

void on_size_request (GtkRequisition *)

This do-nothing callback effectively throws away a size request.

Private Attributes

· perfedit & m_parent

Provides a link to the perfedit that created this object.

int m_h_page_increment

Provides the horizontal page increment for the horizontal scrollbar.

int m_v_page_increment

Provides the vertical page increment for the vertical scrollbar.

• int m_snap

The amount of horizontal snap.

• int m_ppqn

Parts-per-quarter-note value.

int m_page_factor

4096, horizonal page sizing.

int m_divs_per_beat

Holds current tick scaling value.

· int m ticks per bar

Holds current bar scaling value.

• int m perf scale x

Scaling based on zoom and PPQN.

• int m zoom

New value to attempt a rudimentary time-zoom feature.

int m names y

The maximum height of the perfroll names box, in pixes.

int m_background_x

The width of the perfroll background.

· int m size box w

This is a basically constant value set to $s_perfroll_size_box_w = 3$.

int m_measure_length

The legnth of a measure, in beat units.

int m_beat_length

The length of a beat, in parts-per-quarter note.

• midipulse m_old_progress_ticks

Saves the position of the progress bar, for erasing it in preparation for drawing it at the next tick value.

bool m_have_button_press

Used in the fruity and seq24 perfroll input classes to help with trigger push/pop management.

• int m_4bar_offset

Holds the horizontal offset related to the horizontal scroll-bar position.

· int m sequence offset

This value is the vertical version of m_4bar_offset.

· int m roll length ticks

Provides the width of the piano roll in ticks.

midipulse m_drop_tick

The horizontal location for section movement.

midipulse m_drop_tick_trigger_offset

The horizontal trigger location for section movement.

int m_drop_sequence

Holds the currently-selected sequence being moved.

• int m sequence max

Currently, just a class-specific version of c_max_sequence, meant for the future.

bool m_sequence_active [c_max_sequence]

Used when drawing an active sequence.

• FruityPerfInput m_fruity_interaction

We need both styles of interaction object present.

• Seq24PerfInput m_seq24_interaction

Provides support for standard Seq24 mouse handling, plus the keystroke handlers.

bool m moving

Used in the Seq24 or Fruity processing when moving a section of triggers.

bool m_growing

Used in the Seq24 or Fruity processing when growing a section of triggers.

• bool m_grow_direction

Used in the Seq24 or Fruity processing when growing a section of triggers.

Friends

class FruityPerfInput

These friend implement interaction-specific behavior, although only the Seq24 interactions support full keyboard processing, except for some common functionality provided by perform::perfroll_key_event().

- class Seg24PerfInput
- · class perfedit

Additional Inherited Members

12.53.1 Constructor & Destructor Documentation

12.53.1.1 seq64::perfroll::perfroll (perform & perf, perfedit & parent, Gtk::Adjustment & hadjust, Gtk::Adjustment & vadjust, int ppqn = SEQ64_USE_DEFAULT_PPQN)

```
12.53.1.2 seq64::perfroll::~perfroll() [virtual]
```

Well, now there are two objects, so no explicit deletion necessary.

12.53.2 Member Function Documentation

12.53.2.1 void seq64::perfroll::set_guides (int snap, int measure, int beat)

This function then fills in the background, and queues up a draw operation.

Parameters

snap	Provides the number of snap-pulses (pulses per snap interval) as calculated in perfedit::set_guides(). This is actually equal to the measure-pulses divided by the snap value in perfedit; the snap value defaults to 8.
measure	Provides the number of measure-pulses (pulses per measure) as calculated in perfedit::set_guides().
beat	Provides the number of beat-pulses (pulses per beat) as calculated in perfedit::set_guides().

12.53.2.2 void seq64::perfroll::update_sizes ()

Note

Trying to figure out what the 16 is. So take the "bars-visible" calculation, the c_perf_scale_x value, assume that "ticks" is another name for "pulses", and assume that "beats" is a quarter note. Ignoring the numbers, the units come out to:

```
pixels * ticks / pixel
bars = ------
ticks / beat * beats / bar
```

Thus, the 16 is a "beats per bar" or "beats per measure" value. This doesn't quite make sense, but there are 16 divisions per beat on the perfroll user-interface. So for now we'll call it the latter, and make a variable called "m_divs_per_beat", see its definition in the class initializer list.

12.53.2.3 void seq64::perfroll::init_before_show()

First, it gets the largest trigger value among the active sequences. Then it truncates this value to the nearest PPQN * 16 ticks. Then it adds PPQN * 4096 ticks.

```
12.53.2.4 void seq64::perfroll::fill_background_pixmap( )
```

The first thing done is to clear the background by painting it with a filled white rectangle.

This function is called whenever something occurs (e.g. zoom) that can affect how the piano roll is drawn.

```
12.53.2.5 void seq64::perfroll::increment_size ( )
12.53.2.6 void seq64::perfroll::draw_all ( )
```

m_drop_y is adjusted by perfroll::change_vert() for any scroll after it was originally selected. The call below to draw_drawable_row() will have the wrong y location and un-select will not occur if the user scrolls the track up or down to a new y location, if not adjusted.

```
12.53.2.7 void seq64::perfroll::follow_progress( )
12.53.2.8 void seq64::perfroll::redraw_progress( ) [inline]
12.53.2.9 void seq64::perfroll::draw_progress( ) [private]
```

We would like to be able to leave the line there when the progress is paused while running off of JACK transport. How? The perf().get_tick() call always returns 0 when stop is in force.

If we comment out the erasure of the old line, we see that the progress bar is also erased when a pattern boundary is hit (triggers), and when the sequence is stopped by the user.

In order to support true pause in the song editor, we tried to replace perform::get_tick() with perform::get_start_tick() and perform::get_last_tick() [a new experimental function]. But those replacements here always return 0, even as perform::get_tick() increases. Now were are trying a newer function, perform::get_max_tick(), which seems to do the trick for resuming (instead of rewinding) the progress bar. It's still a tiny bit laggy, so we have to find a faster way to get the maximum. (Note that the draw_progress function is called at every timeout, that is, constantly.)

The perform::get_max_tick() call doesn't work with JACK: the progress bar rewinds to the beginning when playback is paused, though it does resume where it left off. It also may cause the progress bar to backtrack through any gap. Let's restore the get tick() call.

```
12.53.2.10 void seq64::perfroll::redraw_dirty_sequences() [private]
```

Change Note ca 2016-05-30 Lets try not drawing sequences greater than the maximum, at all.

```
12.53.2.11 void seq64::perfroll::set_ppqn ( int ppqn ) [private]
```

The m_ticks_per_bar member replaces the global ppqn times 16. This construct is parts-per-quarter-note times 4 quarter notes times 4 sixteenth notes in a bar. (We think...)

The m_perf_scale_x member starts out at c_perf_scale_x, which is 32 ticks per pixel at the default tick rate of 192 PPQN. We adjust this now. But note that this calculation still involves the c_perf_scale_x constant.

Todo Resolve the issue of c_perf_scale_x versus m_perf_scale_x in perfroll.

```
12.53.2.12 void seq64::perfroll::convert_xy ( int x, int y, midipulse & d_tick, int & d_seq ) [private]
```

The results are returned via the d_tick and d_seq parameters. The sequence number is clipped to a legal value (0 to m_sequence_max).

Parameters

	х	The x coordinate of the mouse pointer.
	У	The y coordinate of the mouse pointer.
out	d_tick	Holds the calculated tick value.
out	d_seq	Holds the calculated sequence-number value.

12.53.2.13 void seq64::perfroll::convert_x (int x, midipulse & tick) [private]

The result is returned via the tick parameter.

12.53.2.14 void seq64::perfroll::snap_x(int & x) [private]

- m_snap = number pulses to snap to
- m_perf_scale_x = number of pulses per pixel

Therefore mod = m_snap/m_perf_scale_x equals the number pixels to snap to.

12.53.2.15 void seq64::perfroll::draw_sequence_on(int seqnum) [private]

Statement nesting from hell!

12.53.2.16 void seq64::perfroll::draw_background_on(int seqnum) [private]

12.53.2.17 void seq64::perfroll::draw_drawable_row(long y) [private]

It is involved in the drawing of a greyed (selected) row.

What's weird is that we divide y by m_names_y, then multiply it by m_names_y, before passing the result to draw—drawable(). However, if we just use y casted to an int, then the drawing of the row is only partial, vertically.

```
12.53.2.18 void seq64::perfroll::change_horz( ) [private]
```

Since the m_4bar_offset value is always multiplied by m_ticks_per_bar before usage, let's just do it here and not have to multiply it later.

12.53.2.19 void seq64::perfroll::change_vert() [private]

Stazed;

Must adjust m_drop_y or perfroll_input's unselect_triggers() will not work if scrolled up or down to a new location. See the note in on_button_press_event() in the perfroll_input module. Also see the note in the draw_all() function.

12.53.2.20 void seq64::perfroll::split_trigger (int sequence, midipulse tick) [private]

12.53.2.21 void seq64::perfroll::enqueue_draw() [private]

The parent perfedit will call perfroll::queue_draw() on behalf of this object, and it will pass a perfroll::enqueue_draw() to the peer perfedit's perfroll, if the peer exists.

12.53.2.22 void seq64::perfroll::set_zoom(int z) [private]

Change Note ca 2016-04-05 The initial zoom value is c_perf_scale_x (32). We allow it to range from 1 to 128, for now. Smaller values zoom in.

12.53.2.23 void seq64::perfroll::horizontal_adjust(double step) [inline], [private]

A duplicate of the one in segroll.

Parameters

step F

Provides the step value to use for adjusting the horizontal scrollbar. See gui_drawingarea_gtk2::scroll_hadjust() for more information.

12.53.2.24 void seq64::perfroll::vertical_adjust(double step) [inline], [private]

A near-duplicate of the one in seqroll.

Parameters

step

Provides the step value to use for adjusting the vertical scrollbar. See gui drawingarea gtk2::scroll vadjust() for more information.

12.53.2.25 void seq64::perfroll::horizontal_set (double value) [inline], [private]

Parameters

value

The desired position. Mostly this is either 0.0 or 9999999.0 (an "infinite" value to select the start or end position.

12.53.2.26 void seq64::perfroll::vertical_set (double value) [inline], [private]

Parameters

value

The desired position. Mostly this is either 0.0 or 9999999.0 (an "infinite" value to select the start or end position.

12.53.2.27 void seq64::perfroll::on_realize() [private]

Calls the base-class version first.

Then it allocates the additional resources need, that couldn't be initialized in the constructor, and makes some connections.

Stazed:

This creation of m_background needs to be set to the max width for proper drawing of zoomed measures or they will get truncated with high beats per measure and low beat width. Since this is a constant size, it cannot be adjusted later for zoom. The constant c_perfroll_background_x is set to the max amount by default for use here. The drawing functions fill_background_pixmap() and draw_background_on() which use c_perfroll_background_x also, could be adjusted by zoom with a substituted variable. Not sure if there is any benefit to doing the adjustment... Perhaps a small benefit in speed? Maybe FIXME if really, really bored...

12.53.2.28 bool seq64::perfroll::on_expose_event (GdkEventExpose * ev) [private]

Draws a vertical page of the performance editor. The part drawn starts at m_sequence_offset and continues until the last sequence that can be at least partially seen given the height of the window.

If we're at the bottom of the sequences (1024, a non-existent sequence) would be the last sequence shown, we don't bother drawing it. This prevents debug messages about an illegal sequence, and can show a black bottom row that is a clear sign we're at the end of the legal sequences.

Parameters

ev Provides the expose event.

Returns

Always returns true.

12.53.2.29 bool seq64::perfroll::on_button_press_event(GdkEventButton * ev) [private]

This gives us Seq24 versus Fruity behavior.

One minor issue: Fruity behavior doesn't yet provide the keystroke behavior we now handle for the Seq24 mode of operation.

12.53.2.30 bool seq64::perfroll::on_button_release_event (GdkEventButton * ev) [private]

This gives us Seq24 versus Fruity behavior.

```
12.53.2.31 bool seq64::perfroll::on_motion_notify_event( GdkEventMotion * ev ) [private]
12.53.2.32 bool seq64::perfroll::on_scroll_event( GdkEventScroll * ev ) [private]
```

If the Shift key is held while scrolling, then the scrolling is horizontal, otherwise it is vertical. This matches the convention of the sequedit class.

Note that, unlike the sequest class, Ctrl-Scroll is not used to modify the zoom value. Rather than mess up legacy behavior, we will rely on keystrokes (z, 0, Z, and Ctrl-Page-Up and Ctrl-Page-Down) to implement this zoom.

Parameters

```
ev Provides the scroll event.
```

Returns

Currently always returns true.

```
12.53.2.33 bool seq64::perfroll::on_focus_in_event( GdkEventFocus * ev ) [private]
12.53.2.34 bool seq64::perfroll::on_focus_out_event( GdkEventFocus * ev ) [private]
12.53.2.35 void seq64::perfroll::on_size_allocate( Gtk::Allocation & al ) [private]
12.53.2.36 bool seq64::perfroll::on_key_press_event( GdkEventKey * ev ) [private]
```

If we don't check the event type first, then the ev->keyval value is something weird like 65507. Note that we pass the functionality on to the perform::perfroll_key_event() function for the handling of delete, cut, copy, paste, and undo operations. If the keystroke is not handled by that function, then we handle it here.

Note that only the Seq24 input interaction object handles additional keystrokes not handled by the perfroll_key_ event() function.

The perfroll_key_event() call handles Del, Ctrl-X, Ctrl-V, and Ctrl-Z (which does nothing at present).

We've also added support for moving up and down in the piano roll (Up and Down arrows), paging up and down (Page-Up and Page-Down keys), paging left and right (Shift Page-Up and Page-Down), paging to top and bottom (Home and End), and paging to start and end (Shift Home and End).

The Keypad-End key is an issue on our ASUS "gaming" laptop. Whether it is seen as a "1" or an "End" key depends on an interaction between the Shift and the Num Lock key. Annoying, takes some time to get used to.

Stazed: there are many changes from seq32 that need to be studied before including them here. Note that, even though we filter out the Ctrl key here, it still works for Ctrl-X (cut) and Ctrl-V (paste). For undo, the Undo button can be used, Ctrl-Z never worked in this view anyway.

Warning

We see that 'x' and 'z' are already handled in perfroll_key_event() if the Ctrl key was pressed. Be careful.

```
12.53.2.37 void seq64::perfroll::on_size_request ( GtkRequisition * ) [inline], [private]
```

12.53.3 Friends And Related Function Documentation

```
12.53.3.1 friend class FruityPerfInput [friend]
```

The perfedit class needs access to the private enqueue_draw() function.

```
12.53.3.2 friend class Seq24PerfInput [friend]
```

```
12.53.3.3 friend class perfedit [friend]
```

12.53.4 Field Documentation

```
12.53.4.1 perfedit& seq64::perfroll::m_parent [private]
```

We want to support two perfedit windows, but the children of perfedit will have to communicate changes requiring a redraw through the parent.

```
12.53.4.2 int seq64::perfroll::m_h_page_increment [private]
```

It was set to 1, the same as the step increment. That is too little. This value will be set to 4, for now. Might be a useful "user" configuration option.

```
12.53.4.3 int seq64::perfroll::m_v_page_increment [private]
```

It was set to 1, the same as the step increment. That is too little. This value will be set to 8, for now. Might be a useful "user" configuration option.

```
12.53.4.4 int seq64::perfroll::m_snap [private]
```

```
12.53.4.5 int seq64::perfroll::m_ppqn [private]
```

```
12.53.4.6 int seq64::perfroll::m_page_factor [private]
```

12.53.4.7 int seq64::perfroll::m_divs_per_beat [private]

12.53.4.8 int seq64::perfroll::m_ticks_per_bar [private]

12.53.4.9 int seq64::perfroll::m_perf_scale_x [private]

12.53.4.10 int seq64::perfroll::m_zoom [private]

It seems to work pretty well now.

```
12.53.4.11 int seq64::perfroll::m_names_y [private]
```

This is currently semantically a constant set to c_names_y = 24.

```
12.53.4.12 int seq64::perfroll::m_background_x [private]
```

This is based on the m_ppqn value and the value of c_perf_scale_x (or is m_perf_scale_x preferable?)

```
12.53.4.13 int seq64::perfroll::m_size_box_w [private]
```

It is used in drawing the short lines of the small box that sits at the top-left and bottom-right corners of each segment in the pattern editor. These can be used to lengthen and shorten a section in the song editor. We will increase this size, perhaps double it, to make it easier to grab.

```
12.53.4.14 int seq64::perfroll::m_measure_length [private]
```

```
12.53.4.15 int seq64::perfroll::m_beat_length [private]
```

12.53.4.16 midipulse seq64::perfroll::m_old_progress_ticks [private]

See the draw_progress() function. This could almost be static inside that function.

```
12.53.4.17 bool seq64::perfroll::m_have_button_press [private]
```

```
12.53.4.18 int seq64::perfroll::m_4bar_offset [private]
```

Used in drawing the progress bar and the sequence events. Also used in convert_x() and convert_xy(). This used to be the offset in units of bar ticks, but now we use it as a full-fledged ticks value. See the change horz() function.

```
12.53.4.19 int seq64::perfroll::m_sequence_offset [private]
```

It is obtained or changed when the vertical scroll-bar moves. It is used for drawing the correct vertical window in the piano roll.

```
12.53.4.20 int seq64::perfroll::m_roll_length_ticks [private]
```

Calculated in init_before_show() based on the maximum trigger found in the perform object, the ticks/bar, the $P \leftarrow PQN$, and the page factor. Also can be increased in size in the increment_size() function [tied to the Grow button]. Used in update sizes().

```
12.53.4.21 midipulse seq64::perfroll::m_drop_tick [private]
```

Used only by the friend modules perfroll_input and fruityperfroll_input.

12.53.4.22 midipulse seq64::perfroll::m_drop_tick_trigger_offset [private]

Used only by the friend modules perfroll_input and fruityperfroll_input.

12.53.4.23 int seq64::perfroll::m_drop_sequence [private]

Used for redrawing the sequence.

12.53.4.24 int seq64::perfroll::m_sequence_max [private]

12.53.4.25 bool seq64::perfroll::m_sequence_active[c_max_sequence] [private]

Not sure yet why we can't just use the sequence's member function to access this status boolean.

12.53.4.26 FruityPerfInput seq64::perfroll::m_fruity_interaction [private]

Even if the user specifies the fruity interaction, the Seq24 interaction is still needed to handle our new keystroke support for the perfroll. We need both objects to exist all the time, similar to the Fruity/Seq24 roles in the seqroll object.

Obsolete AbstractPerfInput * m_interaction

12.53.4.27 Seq24PerfInput seq64::perfroll::m_seq24_interaction [private]

12.53.4.28 bool seq64::perfroll::m_moving [private]

12.53.4.29 bool seq64::perfroll::m_growing [private]

12.53.4.30 bool seq64::perfroll::m_grow_direction [private]

Determines whether the section is growing to the left or to the right.

12.54 seq64::perftime Class Reference

This class implements drawing the piano time at the top of the "performance window" (the "song editor"). Inheritance diagram for seq64::perftime:



Public Member Functions

• perftime (perform &perf, perfedit &parent, Gtk::Adjustment &hadjust, int ppqn=SEQ64_USE_DEFAULT_P ← PQN)

Principal constructor.

virtual ~perftime ()

Let's provide a do-nothing virtual destructor.

- · void reset ()
- void set scale (int scale)
- void set_guides (int snap, int measure)

Sets the m_snap value and the m_measure_length members directly from the function parameters, which are in units of pulses (sometimes misleadingly called "ticks".)

· void increment size ()

This function does nothing.

Private Member Functions

• void enqueue draw ()

Wraps queue_draw() and forwards the call to the parent perfedit, so that it can forward it to any other perfedit that exists.

void set zoom (int z)

Implements the horizontal zoom feature.

void draw_background ()

Separated out the drawing done in on_expose_event(), so that it can be redone when the zoom changes.

- void draw_progress_on_window ()
- void change horz ()

Changes the m_4bar_offset and queues a draw operation.

void set_ppqn (int ppqn)

Handles changes to the PPQN value in one place.

long tick_to_pixel (midipulse tick)

Common calculation to convert a pulse/tick value to a perftime x value.

midipulse pixel_to_tick (long pixel)

The inverse of tick_to_pixel().

· int tick offset ()

Centralizes calculation of the tick offset of the time bar.

void update_sizes ()

This function does nothing.

• int idle_progress ()

This function just returns true.

void update_pixmap ()

This function does nothing.

void draw_pixmap_on_window ()

This function does nothing.

• void on_realize ()

Implements the on-realization event, then allocates some resources the could not be allocated in the constructor.

• bool on expose event (GdkEventExpose *ev)

Implements the on-expose event.

bool on_button_press_event (GdkEventButton *ev)

Implement the button-press event to set the L and R ticks.

• void on_size_allocate (Gtk::Allocation &r)

Implements a size-allocation event.

bool on_button_release_event (GdkEventButton *)

This button-release handler does nothing.

bool key_press_event (GdkEventKey *ev)

This callback function handles a key-press event.

Private Attributes

• perfedit & m_parent

Provides a link to the perfedit that created this object.

· int m_4bar_offset

Not yet sure exactly what this member represents.

· int m_tick_offset

This member is m_4bar_offset times 16 times the current PPQN, to save some calculations and centralize this value.

• int m_ppqn

The current value of PPQN, which we are trying to get to work everywhere, when PPQN is changed from the global ppqn = 192.

• int m_snap

Snap value, starts out very small, equal to m_ppqn.

· int m measure length

Provides the length of a measure in pulses or ticks.

· int m left marker tick

Holds the current location of the left (L) marker when arrow movement is in force.

int m_right_marker_tick

Holds the current location of the right (R) marker when arrow movement is in force.

• int m perf scale x

A class version of the global c_perf_scale_x factor.

· int m_timearea_y

A class version of the global c_timerarea_y factor.

Friends

· class perfedit

Additional Inherited Members

12.54.1 Constructor & Destructor Documentation

12.54.1.1 seq64::perftime::perftime (perform & p, perfedit & parent, Gtk::Adjustment & hadjust, int ppqn = SEQ64_USE_DEFAULT_PPQN)

In the constructor you can only allocate colors; get_window() returns 0 because we have not been realized.

Note

Note that we still have to use a global constant in the base-class constructor; we cannot assign it to the corresponding member beforehand.

Parameters

р	Provides a reference to the main performance object of the application.
parent	Provides a reference to the object that contains this object, so that this object can tell the parent to queue up a drawing operation.
hadjust	Provides the horizontal scrollbar object needed so that perftime can respond to scrollbar cursor/thumb movement.
ppqn	An optional override of the default PPQN value for the application.

```
12.54.1.2 virtual seq64::perftime::~perftime( ) [inline], [virtual]
12.54.2 Member Function Documentation
12.54.2.1 void seq64::perftime::reset( )
12.54.2.2 void seq64::perftime::set_scale( int scale )
```

This function then fills in the background, and queues up a draw operation.

12.54.2.3 void seq64::perftime::set_guides (int snap, int measure)

Parameters

snap	Provides the number of snap-pulses (pulses per snap interval) as calculated in perfedit::set_guides (). This is actually equal to the measure-pulses divided by the snap value in perfedit; the snap value defaults to 8.
measure	Provides the number of measure-pulses (pulses per measure) as calculated in perfedit::set_guides().

```
12.54.2.4 void seq64::perftime::increment_size() [inline]
```

Compare it to perfroll::increment_size().

12.54.2.5 void seq64::perftime::enqueue_draw() [private]

The parent perfedit will call perftime::queue_draw() on behalf of this object, and it will pass a perftime::enqueue_cdraw() to the peer perfedit's perftime, if the peer exists.

```
12.54.2.6 void seq64::perftime::set_zoom(int z) [private]
```

Redraws the background if the new zoom checked out.

Parameters

z Provides the zoom value, which is checked, and then copied into m_perf_scale_x.

```
12.54.2.7 void seq64::perftime::draw_background( ) [private]
```

Note that m measure length == 0 will cause integer overflow.

12.54.2.8 void seq64::perftime::draw_progress_on_window() [private]

```
12.54.2.9 void seq64::perftime::change_horz( ) [private]
```

Again, uses the constant, 16 [now offloaded to the new tick_offset() function.].

```
12.54.2.10 void seq64::perftime::set_ppqn(int ppqn) [private]
```

It also modifies m_snap, m_measure_length (but always for four measures!), and m_tick_offset.

Todo We need make the 4 constant variable per the number of beats (quarter-notes) per bar, and also at least make 16 (4x4) a meaningful manifest constant.

Parameters

12.54.2.11 long seq64::perftime::tick_to_pixel(midipulse tick) [inline], [private]

Parameters

tick The horizontal tick value to convert to an x pixel value, based on tick-offset and the x-scale.

Returns

Returns the x-pixel representing the time location parameter.

12.54.2.12 midipulse seq64::perftime::pixel_to_tick(long pixel) [inline], [private]

Parameters

```
pixel The pixel value.
```

Returns

Returns the time value represented b the pixel.

12.54.2.13 int seq64::perftime::tick_offset() [inline], [private]

Returns

Returns m_4bar_offset * 16 * m_ppqn.

```
12.54.2.14 void seq64::perftime::update_sizes() [inline], [private]
12.54.2.15 int seq64::perftime::idle_progress() [inline], [private]
12.54.2.16 void seq64::perftime::update_pixmap() [inline], [private]
12.54.2.17 void seq64::perftime::draw_pixmap_on_window() [inline], [private]
12.54.2.18 void seq64::perftime::on_realize() [private]
```

It is important to call the base-class version of this function.

The former work of this function is now done in base-class's on_realize() and in its constructor now.

```
m_window = get_window();
m_gc = Gdk::GC::create(m_window);
m_window->clear();
set_size_request(10, m_timearea_y);
```

12.54.2.19 bool seq64::perftime::on_expose_event(GdkEventExpose * ev) [private]

Redraws the background.

Note

The perfedit object is created early on. When brought on-screen from mainwand (the main window), first, perftime::on_realize() is called, then this event is called.

Parameters

ev The expose event, not used.

Returns

Always returns true.

```
12.54.2.20 bool seq64::perftime::on_button_press_event ( GdkEventButton * p0 ) [private]
```

Added functionality to try to set the start-tick if ctrl-left-click is pressed.

Parameters

p0 The button event.

Returns

Always returns true.

Why is setting the start-tick disabled? We re-enable it and see if it works. To our surprise, it works, but it sticks between stop/pause and the next playback in the performance editor. We added a feature where stop sets the start-tick to the left tick (or the beginning tick).

```
12.54.2.21 void seq64::perftime::on_size_allocate ( Gtk::Allocation & r ) [private]
```

12.54.2.22 bool seq64::perftime::on button release event (GdkEventButton *) [inline], [private]

"ev", The button event parameter, is not used.

Returns

Always returns false

```
12.54.2.23 bool seq64::perftime::key_press_event( GdkEventKey * ev ) [private]
```

Can't get the keystroke events to be seen by perfroll or perftime here using the normal callback function for keystrokes, and not sure why. The perfedit object can call this function, and that call works, so the perfedit class, which does get keystrokes, calls this function to do the work.

This function uses the "I" key to activate the movement of the "L" marker with the arrow keys, by the interval of on snap value for each press. It also uses the "r" key to activate the movement of the "R" marker, and the "x" to deactivate either movement move.

Be aware that there is no visual feedback, as yet, that one is in the movement mode.

Also be aware the changing the name of this function from "key_press_event()" to "on_key_press_event()" will disrupt the process, causing keystrokes to not get here. Too tricky.

12.54.3 Friends And Related Function Documentation

```
12.54.3.1 friend class perfedit [friend]
```

12.54.4 Field Documentation

```
12.54.4.1 perfedit& seq64::perftime::m_parent [private]
```

We want to support two perfedit windows, but the children of perfedit will have to communicate changes requiring a redraw through the parent.

```
12.54.4.2 int seq64::perftime::m_4bar_offset [private]
```

Also, why always 4/16 in the calculations of this value? Might be able to get rid of this member, though it's a bit tricky.

```
12.54.4.3 int seq64::perftime::m_tick_offset [private]
Why 16?

12.54.4.4 int seq64::perftime::m_ppqn [private]

12.54.4.5 int seq64::perftime::m_snap [private]

12.54.4.6 int seq64::perftime::m_measure_length [private]
```

This value is m_ppqn * 4, though eventually we want to employ a more flexible representation of measure length. Supports perftime's keystroke processing.

```
12.54.4.7 int seq64::perftime::m_left_marker_tick [private]
```

Otherwise it is -1. Supports perftime's keystroke processing.

```
12.54.4.8 int seq64::perftime::m_right_marker_tick [private]
```

Otherwise it is -1. Supports perftime's keystroke processing.

```
12.54.4.9 int seq64::perftime::m_perf_scale_x [private]
```

12.54.4.10 int seq64::perftime::m_timearea_y [private]

12.55 seq64::rc_settings Class Reference

This class contains the options formerly named "global_xxxxxx".

Public Member Functions

• rc_settings ()

Default constructor.

• rc_settings (const rc_settings &rhs)

Copy constructor.

rc_settings & operator= (const rc_settings &rhs)

Principal assignment operator.

• std::string config filespec () const

Constructs the full path and file specification for the "rc" file based on whether or not the legacy Seq24 filenames are being used.

• std::string user_filespec () const

Constructs the full path and file specification for the "user" file based on whether or not the legacy Seq24 filenames are being used.

• void set_defaults ()

Sets the default values.

bool auto_option_save () const

'Getter' function for member m_auto_option_save

· bool legacy format () const

'Getter' function for member m_legacy_format

bool lash_support () const

'Getter' function for member m_lash_support

• bool allow_mod4_mode () const

'Getter' function for member m_allow_mod4_mode

bool allow_snap_split () const

'Getter' function for member m_allow_snap_split

· bool show midi () const

'Getter' function for member m_show_midi

bool priority () const

'Getter' function for member m_priority

· bool stats () const

'Getter' function for member m_stats

· bool pass_sysex () const

'Getter' function for member m pass sysex

bool with_jack_transport () const

'Getter' function for member m_with_jack_transport

• bool with_jack_master () const

'Getter' function for member m_with_jack_master

• bool with_jack_master_cond () const

'Getter' function for member m_with_jack_master_cond

· bool with_jack () const

'Getter' function for member m_with_jack_transport m_with_jack_master, and m_with_jack_master_cond, to save client code some trouble.

bool song_start_mode () const

'Getter' function for member m_song_start_mode,

• bool filter_by_channel () const

'Getter' function for member m_filter_by_channel

• bool manual_alsa_ports () const

'Getter' function for member m_manual_alsa_ports

• bool reveal_alsa_ports () const

'Getter' function for member m_reveal_alsa_ports

bool print_keys () const

'Getter' function for member m_print_keys

· bool device ignore () const

'Getter' function for member m_device_ignore

int device_ignore_num () const

'Getter' function for member m_device_ignore_num

interaction_method_t interaction_method () const

'Getter' function for member m_interaction_method

• const std::string & filename () const

'Getter' function for member m_filename

const std::string & jack_session_uuid () const

 ${\it 'Getter' function for member m_jack_session_uuid}$

const std::string & last used dir () const

'Getter' function for member m_last_used_dir

const std::string & config_directory () const

'Getter' function for member m_config_directory

· const std::string & config_filename () const

'Getter' function for member m_config_filename

const std::string & user_filename () const

'Getter' function for member m_user_filename

const std::string & config_filename_alt () const

'Getter' function for member m_config_filename_alt;

const std::string & user filename alt () const

'Getter' function for member m_user_filename_alt

Protected Member Functions

void auto_option_save (bool flag)

'Setter' function for member m_auto_option_save

void legacy_format (bool flag)

'Setter' function for member m_legacy_format

void lash_support (bool flag)

'Setter' function for member m_lash_support

void allow mod4 mode (bool flag)

'Setter' function for member m_allow_mod4_mode

void allow snap split (bool flag)

'Setter' function for member m allow snap split

void show_midi (bool flag)

'Setter' function for member m_show_midi

void priority (bool flag)

'Setter' function for member m_priority

void stats (bool flag)

'Setter' function for member m_stats

void pass_sysex (bool flag)

'Setter' function for member m_pass_sysex

void with_jack_transport (bool flag)

'Setter' function for member m_with_jack_transport

void with_jack_master (bool flag)

'Setter' function for member m_with_jack_master

void with_jack_master_cond (bool flag)

 ${\it 'Setter' function for member m_with_jack_master_cond}$

void song_start_mode (bool flag)

'Setter' function for member m_song_start_mode,

void filter_by_channel (bool flag)

'Setter' function for member m_filter_by_channel

void manual_alsa_ports (bool flag)

'Setter' function for member m_manual_alsa_ports

void reveal_alsa_ports (bool flag)

'Setter' function for member m_reveal_alsa_ports

void print_keys (bool flag)

'Setter' function for member m_print_keys

· void device_ignore (bool flag)

'Setter' function for member m_device_ignore

• void device ignore num (int value)

'Setter' function for member m_device_ignore_num However, please note that this value, while set in the options processing of the main module, does not appear to be used anywhere in the code in seq24, Sequencer24, and this application.

void interaction_method (interaction_method_t value)

'Setter' function for member m_interaction_method

void filename (const std::string &value)

'Setter' function for member m filename

void jack_session_uuid (const std::string &value)

'Setter' function for member m_jack_session_uuid

• void last_used_dir (const std::string &value)

'Setter' function for member m_last_used_dir

void config_directory (const std::string &value)

'Setter' function for member m config directory

• void set_config_files (const std::string &value)

'Setter' function for member m_config_filename and m_user_filename

• void config_filename (const std::string &value)

'Setter' function for member m_config_filename ("rc")

• void user_filename (const std::string &value)

'Setter' function for member m_user_filename ("usr")

void config_filename_alt (const std::string &value)

'Setter' function for member m_config_filename_alt

void user_filename_alt (const std::string &value)

'Setter' function for member m_user_filename_alt

Private Member Functions

• std::string home_config_directory () const

Provides the directory for the configuration file, and also creates the directory if necessary.

Private Attributes

· bool m_auto_option_save

[auto-option-save] setting.

bool m_legacy_format

Write files in legacy format.

• bool m_lash_support

Enable LASH, if compiled in.

• bool m_allow_mod4_mode

Allow Mod4 to hold drawing mode.

• bool m_allow_snap_split

Allow snap-split of a trigger.

• bool m_show_midi

Show MIDI events to console.

• bool m_priority

Run at high priority (Linux only).

· bool m stats

Show some output statistics.

bool m_pass_sysex

Pass SysEx to outputs, not ready.

· bool m with jack transport

Enable synchrony with JACK.

bool m_with_jack_master

Serve as a JACK transport Master.

bool m_with_jack_master_cond

Serve as JACK Master if possible.

· bool m song start mode

True is song mode, false is live.

bool m_filter_by_channel

Record only sequence channel data.

• bool m_manual_alsa_ports

[manual-alsa-ports] setting.

· bool m reveal alsa ports

[reveal-alsa-ports] setting.

bool m_print_keys

Show hot-key in main window slot.

• bool m_device_ignore

From seq24 module, unused!

· int m device ignore num

From seg24 module, unused!

· interaction_method_t m_interaction_method

[interaction-method]

• std::string m_filename

Provides the name of current MIDI file.

· std::string m jack session uuid

Holds the JACK UUID value that makes this JACK connection unique.

std::string m_last_used_dir

Holds the directory from which the last MIDI file was opened (or saved).

• std::string m_config_directory

Holds the current "rc" and "user" configuration directory.

• std::string m_config_filename

Holds the current "rc" configuration filename.

std::string m_user_filename

Holds the current "user" configuration filename.

• std::string m_config_filename_alt

Holds the legacy "rc" filename, ".seq24rc".

• std::string m user filename alt

Holds the legacy "user" filename, ".seq24usr".

Friends

- · class optionsfile
- · class options
- class mainwnd
- int parse_command_line_options (int argc, char *argv[])

Parses the command-line options on behalf of the application.

bool help_check (int argc, char *argv[])

Checks to see if the first option is a help or version argument, just so we can skip the "Reading configuration ..." messages.

12.55.1 Detailed Description

It gives us a whole lot more encapsulation and control over how the options of the "rc" file (optionsfile) are set and used. Note that this class does not support the hot-keys options; those are handled in the keys_perform class.

12.55.2 Constructor & Destructor Documentation

```
12.55.2.1 seq64::rc_settings::rc_settings ( )
```

12.55.2.2 seq64::rc_settings::rc_settings (const rc_settings & rhs)

Parameters

```
rhs The source of the data for the copy.
```

12.55.3 Member Function Documentation

12.55.3.1 rc_settings & seq64::rc_settings::operator= (const rc_settings & rhs)

Parameters

rhs The source of the data for the assignment.

Returns

Returns a reference to the destination for use in serial assignments.

```
12.55.3.2 std::string seq64::rc_settings::config_filespec ( ) const
```

Returns

If home_config_directory() returns a non-empty string, then the legacy or normal "rc" configuration file-name is appended to that result, and returned. Otherwise, an empty string is returned.

```
12.55.3.3 std::string seq64::rc_settings::user_filespec ( ) const
```

Returns

If home_config_directory() returns a non-empty string, then the legacy or normal "user" configuration file-name is appended to that result, and returned. Otherwise, an empty string is returned.

```
12.55.3.4 void seq64::rc_settings::set_defaults()

12.55.3.5 bool seq64::rc_settings::auto_option_save() const [inline]

12.55.3.6 bool seq64::rc_settings::legacy_format() const [inline]

12.55.3.7 bool seq64::rc_settings::lash_support() const [inline]

12.55.3.8 bool seq64::rc_settings::allow_mod4_mode() const [inline]
```

```
12.55.3.9 bool seq64::rc_settings::allow_snap_split() const [inline]
12.55.3.10 bool seq64::rc_settings::show_midi( ) const [inline]
12.55.3.11 bool seq64::rc_settings::priority() const [inline]
12.55.3.12 bool seq64::rc_settings::stats ( ) const [inline]
12.55.3.13 bool seq64::rc_settings::pass_sysex() const [inline]
12.55.3.14 bool seq64::rc_settings::with_jack_transport( ) const [inline]
12.55.3.15 bool seq64::rc_settings::with_jack_master( ) const [inline]
12.55.3.16 bool seq64::rc_settings::with_jack_master_cond() const [inline]
12.55.3.17 bool seq64::rc_settings::with_jack( ) const [inline]
12.55.3.18 bool seq64::rc_settings::song_start_mode( ) const [inline]
12.55.3.19 bool seq64::rc_settings::filter_by_channel( ) const [inline]
12.55.3.20 bool seq64::rc_settings::manual_alsa_ports ( ) const [inline]
12.55.3.21 bool seq64::rc_settings::reveal_alsa_ports() const [inline]
12.55.3.22 bool seq64::rc_settings::print_keys( ) const [inline]
12.55.3.23 bool seq64::rc_settings::device_ignore( ) const [inline]
12.55.3.24 int seq64::rc_settings::device_ignore_num() const [inline]
12.55.3.25
          interaction_method_t seq64::rc_settings::interaction_method( ) const [inline]
12.55.3.26 const std::string& seq64::rc_settings::filename( ) const [inline]
12.55.3.27 const std::string& seq64::rc_settings::jack_session_uuid( ) const [inline]
12.55.3.28 const std::string& seq64::rc_settings::last_used_dir( ) const [inline]
12.55.3.29 const std::string& seq64::rc_settings::config_directory( ) const [inline]
12.55.3.30 const std::string& seq64::rc_settings::config_filename() const [inline]
12.55.3.31 const std::string& seq64::rc_settings::user_filename( ) const [inline]
```

```
const std::string& seq64::rc_settings::config_filename_alt( ) const [inline]
12.55.3.33
          const std::string& seq64::rc_settings::user_filename_alt( ) const [inline]
12.55.3.34
          void seq64::rc_settings::auto_option_save( bool flag ) [inline], [protected]
12.55.3.35
          void seq64::rc_settings::legacy_format( bool flag ) [inline], [protected]
12.55.3.36
          void seq64::rc_settings::lash_support( bool flag ) [inline], [protected]
12.55.3.37
          void seq64::rc_settings::allow_mod4_mode( bool flag ) [inline], [protected]
12.55.3.38
          void seq64::rc_settings::allow_snap_split( bool flag ) [inline], [protected]
12.55.3.39
          void seq64::rc_settings::show_midi( bool flag ) [inline], [protected]
12.55.3.40 void seq64::rc_settings::priority ( bool flag ) [inline], [protected]
12.55.3.41
          void seq64::rc_settings::stats ( bool flag ) [inline], [protected]
12.55.3.42 void seq64::rc_settings::pass_sysex(bool flag) [inline], [protected]
12.55.3.43
          void seq64::rc_settings::with_jack_transport( bool flag ) [inline], [protected]
          void seq64::rc_settings::with_jack_master( bool flag ) [inline], [protected]
12.55.3.45 void seq64::rc_settings::with_jack_master_cond(bool flag) [inline], [protected]
12.55.3.46
          void seq64::rc_settings::song_start_mode( bool flag ) [inline], [protected]
          void seq64::rc_settings::filter_by_channel( bool flag ) [inline], [protected]
12.55.3.48 void seq64::rc_settings::manual_alsa_ports ( bool flag ) [inline], [protected]
12.55.3.49
          void seq64::rc_settings::reveal_alsa_ports ( bool flag ) [inline], [protected]
12.55.3.50
          void seq64::rc_settings::print_keys ( bool flag ) [inline], [protected]
          void seq64::rc_settings::device_ignore ( bool flag ) [inline], [protected]
12.55.3.51
12.55.3.52 void seq64::rc_settings::device_ignore_num ( int value ) [protected]
Parameters
```

The value to use to make the setting.

12.55.3.53 void seq64::rc_settings::interaction_method(interaction_method_t value) [protected]

Parameters

value	The value to use to make the setting.
-------	---------------------------------------

12.55.3.54 void seq64::rc_settings::filename (const std::string & value) [protected]

Parameters

value	The value to use to make the setting.
-------	---------------------------------------

12.55.3.55 void seq64::rc_settings::jack_session_uuid (const std::string & value) [protected]

Parameters

value	The value to use to make the setting.
-------	---------------------------------------

12.55.3.56 void seq64::rc_settings::last_used_dir(const std::string & value) [protected]

Parameters

	value	The value to use to make the setting.	
--	-------	---------------------------------------	--

12.55.3.57 void seq64::rc_settings::config_directory (const std::string & value) [protected]

Parameters

value The value to use to make the setting.	
---	--

12.55.3.58 void seq64::rc_settings::set_config_files (const std::string & value) [protected]

Implements the -config option to change both configuration files ("rc" and "usr") with one option.

Parameters

value	The value to use to make the setting, if the string is not empty. If the value has an extension, it is
	stripped first.

12.55.3.59 void seq64::rc_settings::config_filename (const std::string & value) [protected]

Parameters

value	The value to use to make the setting, if the string is not empty. If there is no period in the string, then	
	".rc" is appended to the end of the filename.	

12.55.3.60 void seq64::rc_settings::user_filename (const std::string & value) [protected]

Parameters

value	The value to use to make the setting, if the string is not empty. If there is no period in the string, then
	".usr" is appended to the end of the filename.

12.55.3.61 void seq64::rc settings::config filename_alt (const std::string & value) [protected]

Parameters

V	alue	The value to use to make the setting, if the string is not empty.

12.55.3.62 void seq64::rc_settings::user_filename_alt (const std::string & value) [protected]

Parameters

value	The value to use to make the setting.	
-------	---------------------------------------	--

12.55.3.63 std::string seq64::rc_settings::home_config_directory() const [private]

If the legacy format is in force, then the home directory for the configuration is (in Linux) "/home/username", and the configuration file is ".seq24rc".

If the new format is in force, then the home directory is (in Linux) "/home/username/.config/sequencer64", and the configuration file is "sequencer64.rc".

Returns

Returns the selected home configuration directory. If it does not exist, or could not be created, then an empty string is returned.

12.55.4 Friends And Related Function Documentation

```
12.55.4.1 friend class optionsfile [friend]
12.55.4.2 friend class options [friend]
12.55.4.3 friend class mainwnd [friend]
12.55.4.4 int parse_command_line_options (int argc, char * argv[]) [friend]
```

Note that, since we call this function twice (once before the configuration files are parsed, and once after), we have to make sure that the global value optind is reset to 0 before calling this function. Note that the traditional reset value for optind is 1, but 0 is used in GNU code to trigger the internal initialization routine of get opt().

Parameters

argc	The number of command-line arguments.
argv	The array of command-line argument pointers.

Returns

Returns the value of optind if no help-related options were provided.

```
12.55.4.5 bool help_check (int argc, char * argv[]) [friend]
```

Also check for the –legacy option. Finally, it also checks for the "?" option that people sometimes use as a guess to get help.

Parameters

argc	The number of command-line arguments.
argv	The array of command-line argument pointers.

Returns

Returns true only if -V, -version, -h, -help, or "?" were encountered. If the legacy options occurred, then rc().legacy_format(true) is called, as a side effect, because it will be needed before we parse the options.

12.55.5 Field Documentation

```
12.55.5.1 bool seq64::rc_settings::m_auto_option_save [private]

12.55.5.2 bool seq64::rc_settings::m_legacy_format [private]

12.55.5.3 bool seq64::rc_settings::m_lash_support [private]

12.55.5.4 bool seq64::rc_settings::m_allow_mod4_mode [private]

12.55.5.5 bool seq64::rc_settings::m_allow_snap_split [private]

12.55.5.6 bool seq64::rc_settings::m_show_midi [private]

12.55.5.7 bool seq64::rc_settings::m_priority [private]

12.55.5.8 bool seq64::rc_settings::m_stats [private]

12.55.5.9 bool seq64::rc_settings::m_pass_sysex [private]

12.55.5.10 bool seq64::rc_settings::m_with_jack_transport [private]
```

```
12.55.5.11 bool seq64::rc_settings::m_with_jack_master [private]
12.55.5.12 bool seq64::rc_settings::m_with_jack_master_cond [private]
12.55.5.13 bool seq64::rc_settings::m_song_start_mode [private]
12.55.5.14 bool seq64::rc_settings::m_filter_by_channel [private]
12.55.5.15 bool seq64::rc_settings::m_manual_alsa_ports [private]
12.55.5.16 bool seq64::rc_settings::m_reveal_alsa_ports [private]
12.55.5.17 bool seq64::rc_settings::m_print_keys [private]
12.55.5.18 bool seq64::rc_settings::m_device_ignore [private]
12.55.5.19 int seq64::rc_settings::m_device_ignore_num [private]
12.55.5.20 interaction_method_t seq64::rc_settings::m_interaction_method [private]
12.55.5.21 std::string seq64::rc_settings::m_filename [private]
12.55.5.22 std::string seq64::rc_settings::m_jack_session_uuid [private]
12.55.5.23 std::string seq64::rc_settings::m_last_used_dir [private]
12.55.5.24 std::string seq64::rc_settings::m_config_directory [private]
This value is "\sim/.config/sequencer64" by default.
12.55.5.25 std::string seq64::rc_settings::m_config_filename [private]
This value is "sequencer64.rc" by default.
12.55.5.26 std::string seq64::rc_settings::m_user_filename [private]
This value is "sequencer64.usr" by default.
12.55.5.27 std::string seq64::rc_settings::m_config_filename_alt [private]
12.55.5.28 std::string seq64::rc_settings::m_user_filename_alt [private]
```

12.56 seq64::rect Class Reference

A small helper class representing a rectangle.

Data Fields

int x

The x-coordinate of the origin of the rectangle.

int y

The y-coordinate of the origin of the rectangle.

· int height

The height of the rectangle, in units of pixels.

· int width

The width of the rectangle, in units of pixels.

12.56.1 Field Documentation

```
12.56.1.1 int seq64::rect::x
```

12.56.1.2 int seq64::rect::y

12.56.1.3 int seq64::rect::height

12.56.1.4 int seq64::rect::width

12.57 seq64::gui_drawingarea_gtk2::rect Struct Reference

A small helper structure representing a rectangle.

Data Fields

- int x
- int y
- int height
- int width

12.57.1 Field Documentation

12.57.1.1 int seq64::gui_drawingarea_gtk2::rect::x

12.57.1.2 int seq64::gui_drawingarea_gtk2::rect::y


12.57.1.3 int seq64::gui_drawingarea_gtk2::rect::height

12.57.1.4 int seq64::gui_drawingarea_gtk2::rect::width

12.58 seq64::Seq24PerfInput Class Reference

Implements the default (Seq24) performance input characteristics of this application.

Inheritance diagram for seq64::Seq24PerfInput:



Public Member Functions

- Seq24PerfInput ()
- bool on button press event (GdkEventButton *a ev, perfroll &roll)

Handles the normal variety of button-press event.

• bool on_button_release_event (GdkEventButton *a_ev, perfroll &roll)

Handles various button-release events.

• bool on_motion_notify_event (GdkEventMotion *a_ev, perfroll &roll)

Handles the normal motion-notify event.

Private Member Functions

• void set_adding (bool a_adding, perfroll &roll)

A popup menu (which one?) calls this.

• bool handle_motion_key (bool is_left, perfroll &roll)

Handles the keystroke motion-notify event for moving a pattern back and forth in the performance.

• bool is_adding () const

'Getter' function for member m_adding

Private Attributes

• bool m_adding

Indicates we are in the middle of adding a sequence segment to the performance.

• midipulse m_effective_tick

The current tick for the current segment?

Friends

· class perfroll

Additional Inherited Members

```
12.58.1 Constructor & Destructor Documentation
```

```
12.58.1.1 seq64::Seq24PerfInput::Seq24PerfInput() [inline]
```

12.58.2 Member Function Documentation

```
12.58.2.1 bool seq64::Seq24Perfinput::on_button_press_event ( GdkEventButton * ev, perfroll & roll ) [virtual]
```

Is there any easy way to use ctrl-left-click as the middle button here?

Returns

Returns true if a modification occurred.

Implements seq64::AbstractPerfInput.

```
12.58.2.2 bool seq64::Seq24PerfInput::on_button_release_event ( GdkEventButton * ev, perfroll & roll ) [virtual]
```

Any use for the middle-button or ctrl-left-click we can add?

Returns

Returns true if any modification occurred.

Implements seq64::AbstractPerfInput.

```
12.58.2.3 bool seq64::Seq24PerfInput::on_motion_notify_event( GdkEventMotion * ev, perfroll & roll ) [virtual]
```

Returns

Returns true if a modification occurs. This function used to always return true.

Implements seq64::AbstractPerfInput.

12.58.2.4 void seq64::Seq24PerfInput::set_adding (bool adding, perfroll & roll) [private]

What does it mean?

```
12.58.2.5 bool seq64::Seq24PerfInput::handle_motion_key ( bool is_left, perfroll & roll ) [private]
```

What happens when the mouse is used to drag the pattern is that, first, roll.m_drop_tick is set by left-clicking into the pattern to select it. As the pattern is dragged, the drop-tick value does not change, but the tick (converted from the moving x value) does.

Then the button-handler sets roll.m_moving = true, and calculates roll.m_drop_tick_trigger_offset = roll.m_drop_tick - p.get_sequence(dropseq)->selected_trigger_start();

The motion handler sees that roll.m_moving is true, gets the new tick value from the new x value, offsets it, and calls p.get_sequence(dropseq)->move_selected_triggers_to(tick, true).

When the user releases the left button, then roll.m_growing is turned of and the roll draw_all()'s.

Parameters

is_left	False denotes the right arrow key, and true denotes the left arrow key.
roll	Provides a reference to the parent roll, which keeps track of most of the information about the status of
	the window.

Returns

Returns true if there was some action able to happen that would necessitate a window update. We've updated triggers::move_selected() [called indirectly near the end of this routine] to return false if no more movement could be made. This prevents this routine from moving way ahead after movement of the selected (in the user-interface) trigger stops.

```
12.58.2.6 bool seq64::Seq24PerfInput::is_adding( )const [inline],[private]
```

12.58.3 Friends And Related Function Documentation

12.58.3.1 friend class perfroll [friend]

12.58.4 Field Documentation

12.58.4.1 bool seq64::Seq24PerfInput::m_adding [private]

12.58.4.2 midipulse seq64::Seq24PerfInput::m_effective_tick [private]

12.59 seg64::Seg24SegEventInput Struct Reference

This structure implement the normal interaction methods for Seq24.

Public Member Functions

Seq24SeqEventInput ()

Default constructor.

void set_adding (bool adding, seqevent &ths)

Changes the mouse cursor to a pencil or a left pointer in the given seqevent object, depending on the first parameter.

• bool on_button_press_event (GdkEventButton *ev, seqevent &ths)

Implements the on-button-press event callback.

• bool on_button_release_event (GdkEventButton *ev, seqevent &ths)

Implements the on-button-release callback.

bool on_motion_notify_event (GdkEventMotion *ev, seqevent &ths)

Implements the on-motion-notify event.

Data Fields

· bool m_adding

True if we're adding events via the mouse.

12.59.1 Constructor & Destructor Documentation

12.59.1.1 seq64::Seq24SeqEventInput::Seq24SeqEventInput() [inline]

12.59.2 Member Function Documentation

12.59.2.1 void seq64::Seq24SeqEventInput::set_adding (bool adding, seqevent & seqev)

Modifies m_adding as well.

Parameters

adding	The value to set m_adding to, and if true, sets the mouse cursor to a pencil icon, otherwise sets it to a standard mouse-pointer icon.
seqev	The seqevent whose window will be set to "adding" mode.

12.59.2.2 bool seq64::Seq24SeqEventInput::on_button_press_event (GdkEventButton * ev, seqevent & seqev)

Set values for dragging, then reset the box that holds dirty redraw spot. Then do the rest.

Parameters

ev	The button event for the press of a mouse button.	
seqev	Provides the sequeent strip to be affected by this button event.	

Returns

Returns true if a likely modification was made. This function used to return true all the time.

Needs update. seqev.m_seq.unselect(); ???????

12.59.2.3 bool seq64::Seq24SeqEventInput::on_button_release_event (GdkEventButton * ev, seqevent & seqev)

Parameters

ev	The button event for the release of a mouse button.	
seqev	Provides the seqevent strip to be affected by this button event.	

Returns

Returns true if a likely modification was made. This function used to return true all the time.

12.59.2.4 bool seq64::Seq24SeqEventInput::on_motion_notify_event (GdkEventMotion * ev, seqevent & seqev)

Parameters

ev	The button event for the motion of the mouse cursor.	
seqev	Provides the sequeent strip to be affected by this button event.	

Returns

Returns true if a likely modification was made. This function used to return true all the time.


12.59.3 Field Documentation

12.59.3.1 bool seq64::Seq24SeqEventInput::m_adding

12.60 seq64::seqdata Class Reference

This class supports drawing piano-roll eventis on a window.

Inheritance diagram for seq64::seqdata:



Public Member Functions

- seqdata (sequence &seq, perform &p, int zoom, Gtk::Adjustment &hadjust)

 Principal constructor.
- virtual ∼seqdata ()

Let's provide a do-nothing virtual destructor.

• void reset ()

This function calls update_size().

void redraw ()

Calls change_horz() to update the pixmap and queue up a redraw operation.

void set zoom (int a zoom)

Sets the zoom to the given value and resets the view via the reset function.

void set_data_type (midibyte status, midibyte control)

Sets the status to the given value, and the control to the optional given value, which defaults to 0, then calls redraw().

Private Member Functions

• int idle_redraw ()

Draws events on this object's built-in window and pixmap.

void update_sizes ()

Updates the sizes in the pixmap if the view is realized, and queues up a draw operation.

void update_pixmap ()

Simply calls draw_events_on_pixmap().

void draw_line_on_window ()

Draws on vertical line on the data window.

void xy_to_rect (int x1, int y1, int x2, int y2, int &rx, int &ry, int &rw, int &rh)

This function takes two points, and returns an XWin rectangle, returned via the last four parameters.

void draw_events_on (Glib::RefPtr< Gdk::Drawable > drawable)

Draws events on the given drawable object.

• void change horz ()

Change the scrolling offset on the x-axis, and redraw.

void convert_x (int x, midipulse &tick)

This function takes screen coordinates, and gives the horizontaol tick value based on the current zoom, returned via the second parameter.

• void render number (Glib::RefPtr< Gdk::Pixmap > &pixmap, int x, int y, const char *const num)

Convenience function for rendering numbers.

void draw_events_on_pixmap ()

Simply calls draw_events_on() for this object's built-in pixmap.

• void draw pixmap on window ()

Simply queues up a draw operation.

void on_realize ()

Implements the on-realization event, by calling the base-class version and then allocating the resources that could not be allocated in the constructor.

• bool on expose event (GdkEventExpose *ev)

Implements the on-expose event by calling draw_drawable() on the event.

bool on_button_press_event (GdkEventButton *ev)

Implements a mouse button-press event.

bool on_button_release_event (GdkEventButton *ev)

Implement a button-release event.

bool on_motion_notify_event (GdkEventMotion *ev)

Handles a motion-notify event.

bool on_leave_notify_event (GdkEventCrossing *ev)

Handles an on-leave notification event.

• bool on_scroll_event (GdkEventScroll *ev)

Implements the on-scroll event.

• void on_size_allocate (Gtk::Allocation &)

Handles a size-allocation event by updating m_window_x and m_window_y, and then updating all of the sizes of the data pane in update_sizes().

Private Attributes

• sequence & m_seq

Points to the sequence whose data is being affected by this class.

• int m zoom

Sets the zoom value for this part of the sequence editor, one pixel == m_zoom ticks, i.e.

• int m_scroll_offset_ticks

The value of the leftmost tick in the data pane.

int m_scroll_offset_x

The value of the leftmost pixel in the data pane.

• int m_number_w

The adjusted width of a digit in a data number.

· int m_number_h

The adjusted height of all digits in a data number.

• int m_number_offset_y

A new value to make it easier to adapt the vertical number drawing of a data item's numeric value to a different font.

midibyte m_status

Holds the status byte of the next event in the sequence, and indicates What the data window is currently editing or drawing.

• midibyte m_cc

Holds the MIDI CC byte of the next event in the sequence, and indicates What the data window is currently editing or drawing.

Glib::RefPtr< Gdk::Pixmap > m_numbers [c_dataarea_y]

Holds the pixmaps for each number (0 to 127) that can be drawn for a data value in the data pane.

GdkRectangle m_old

This rectangle is used in blanking out a data line in draw_line_on_window().

· bool m_dragging

This value is true if the mouse is being dragged in the data pane, which is done in order to change the height and value of each data line.

Friends

- · class Ifownd
- · class seqevent
- · class segroll

Additional Inherited Members

12.60.1 Constructor & Destructor Documentation

12.60.1.1 seq64::seqdata::seqdata (sequence & seq, perform & p, int zoom, Gtk::Adjustment & hadjust)

In the constructor one can only allocate colors, get_window() returns 0 because this pane has not yet been realized.

Parameters

seq	The sequence that is being displayed and edited by this data pane.	
р	The performance object that oversees all of the sequences. This object is needed here only to access the perform::modify() function.	
zoom	The starting zoom of this pane.	
hadjust Generated by	The horizontal adjustment object provided by the parent class, seqedit, that created this pane.	

```
12.60.1.2 virtual seq64::seqdata::~seqdata() [inline], [virtual]
```

12.60.2 Member Function Documentation

```
12.60.2.1 void seq64::seqdata::reset ( )
```

Then, regardless of whether the view is realized, updates the pixmap and queues up a draw operation.

Note

If it weren't for the is_realized() condition, we could just call update_sizes(), which does all this anyway.

```
12.60.2.2 void seq64::seqdata::redraw( ) [inline]
```

```
12.60.2.3 void seq64::seqdata::set_zoom ( int z )
```

Called by seqedit::set zoom(), which validates the zoom value.

Parameters

12.60.2.4 void seq64::seqdata::set_data_type (midibyte status, midibyte control)

Perhaps we should check that at least one of the parameters causes a change.

Parameters

status	The MIDI event byte (status byte) to set.
control	The MIDI CC value to set.

```
12.60.2.5 int seq64::seqdata::idle_redraw( ) [private]
```

This drawing is done only if there is no dragging in progress, to guarantee no flicker.

```
12.60.2.6 void seq64::seqdata::update_sizes( ) [private]
```

It creates a pixmap with window dimensions given by m_window_x and m_window_y.

We thought there was a potential memory leak, since m_pixmap is created every time the window is resized, but valgrind says otherwise... maybe. An awful lot of Gtk leaks!

```
12.60.2.7 void seq64::seqdata::update_pixmap() [private]
```

12.60.2.8 void seq64::seqdata::draw_line_on_window() [private]

12.60.2.9 void seq64::seqdata::xy_to_rect(int x1, int y1, int x2, int y2, int & rx, int & ry, int & rw, int & rh) [private]

It checks the mins/maxes, then fills in x, y, and width, height.

Parameters

	x1	The input x value for the first data point.	
y1 The input y value for the first data point.		The input y value for the first data point.	
	x2	The input x value for the second data point.	
	y2	The input y value for the second data point.	
out	rx	The output for the x value of the XWin rectangle.	
out	ry	The output for the y value of the XWin rectangle.	
out	rw	The output for the width value of the XWin rectangle.	
out	rh	The output for the height of the XWin rectangle.	

12.60.2.10 void seq64::seqdata::draw_events_on(Glib::RefPtr< Gdk::Drawable > drawable) [private]

Very similar to sequent :: draw events on(). And yet it doesn't handle zooming as well, must fix!

Stazed:

For Note On there can be multiple events on the same vertical in which the selected item can be covered. For Note On the selected item needs to be drawn last so it can be seen. So, for other events the variable num_selected_events will be -1 for ALL_EVENTS. For Note On only, the variable will be the number of selected events. If 0 then only one pass is needed. If > 0 then two passes are needed, one for unselected (first), and one for selected (last). For the first pass, if any events are selected, the selection type is EVENTS_UNSELECTED. For the second pass, it will be set to num_selected_events.

We now draw the data line for selected event in dark orange, instead of black. We're not likely to adopt the Stazed convention of drawing in blue. Also, there seem to be some bugs in how the data selection works. Needs more evaluation.

Also, if we decide to draw handle on each vertical data line, it would look nicer if a circle.

Parameters

drawable	The given drawable object.

12.60.2.11 void seg64::segdata::change_horz() [private]

Basically identical to seqevent::change_horz().

```
12.60.2.12 void seq64::seqdata::convert_x ( int x, midipulse & tick ) [inline], [private]
```

12.60.2.13 void seq64::seqdata::render_number (Glib::RefPtr< Gdk::Pixmap > & pixmap, int x, int y, const char *const num) [inline], [private]

Parameters

pixmap	The reference pointer to the GDK pixmap onto which this number will be drawing.
Х	The x-coordinate of the position of the text.
У	The y-coordinate of the position of the text.
num	The number to be rendered. This should be a string reference, but oh well.

```
12.60.2.14 void seq64::seqdata::draw_events_on_pixmap() [inline], [private]
12.60.2.15 void seq64::seqdata::draw_pixmap_on_window() [inline], [private]
12.60.2.16 void seq64::seqdata::on_realize() [private]
```

It also connects up the change_horz() function.

Note that this function creates a small pixmap for every possible y-value, where y ranges from 0 to MIDI_COUNT \leftarrow _MAX-1 = 127. It then fills each pixmap with a numeric representation of that y value, up to three digits (left-padded with spaces).

```
12.60.2.17 bool seq64::seqdata::on_expose_event( GdkEventExpose * ev ) [private]
```

Parameters

ev	Provides the expose-event.
----	----------------------------

Returns

Always returns true.

12.60.2.18 bool seq64::seqdata::on_button_press_event(GdkEventButton * ev) [private]

This function pushes the undo information for the sequence, sets the drop-point, resets the box that holds dirty redraw spot, and sets m_dragging to true.

Parameters

ev	Provides the button-press event.
----	----------------------------------

Returns

Always returns true.

12.60.2.19 bool seq64::seqdata::on_button_release_event(GdkEventButton * ev) [private]

Sets the current point. If m_dragging is true, then the sequence data is changed, the performance modification flag is set, and m_dragging is reset.

Parameters

ev Provides the button-release event.

Returns

Returns true if a modification occurred, and in that case also sets the perform modification flag.

12.60.2.20 bool seq64::seqdata::on_motion_notify_event(GdkEventMotion * ev) [private]

It converts the x,y of the mouse to ticks, then sets the events in the event-data-range, updates the pixmap, draws events in the window, and draws a line on the window.

Parameters

ev The motion event.

Returns

Returns true if a change in event data occurred. If true, then the perform modification flag is set.

12.60.2.21 bool seq64::seqdata::on_leave_notify_event (GdkEventCrossing * ev) [private]

Parameter "p0", the crossing point for the event, is unused.

12.60.2.22 bool seq64::seqdata::on_scroll_event(GdkEventScroll * ev) [private]

This scroll event only handles basic scrolling, without any modifier keys such as the Ctrl of Shift masks. If there is a note (seqroll pane) or event (seqevent pane) selected, and mouse hovers over the data area (seqdata pane), then this scrolling action will increase or decrease the value of the data item, which lengthens of shortens the line drawn.

Todo DOCUMENT the seqdata scrolling behavior in the documentation projects.

Parameters

ev Provides the scroll-event.

Returns


Always returns true.

```
12.60.2.23 void seq64::seqdata::on_size_allocate ( Gtk::Allocation & r ) [private]
Parameters
 r Provides the allocation event.
12.60.3 Friends And Related Function Documentation
12.60.3.1 friend class Ifownd [friend]
12.60.3.2 friend class sequent [friend]
12.60.3.3 friend class segroll [friend]
12.60.4 Field Documentation
12.60.4.1 sequence& seq64::seqdata::m_seq [private]
12.60.4.2 int seq64::seqdata::m_zoom [private]
the unit is ticks/pixel.
12.60.4.3 int seq64::seqdata::m_scroll_offset_ticks [private]
Adjusted in the <a href="mailto:change_horz">change_horz</a>() function.
12.60.4.4 int seq64::seqdata::m_scroll_offset_x [private]
Adjusted in the change_horz() function. It is the offset ticks divided by the zoom value, i.e. the unit is pixels..
12.60.4.5 int seq64::seqdata::m_number_w [private]
By "adjusted", well this is just a minor tweak for appearances.
12.60.4.6 int seq64::seqdata::m_number_h [private]
Basically, the character height times 3. By "adjusted", well this is just a minor tweak for appearances.
12.60.4.7 int seq64::seqdata::m_number_offset_y [private]
```

This value was hardwired as 8, for a character height of 10.



Inheritance diagram for seq64::seqedit:



Public Member Functions

- seqedit (perform &perf, sequence &seq, int pos, int ppqn=SEQ64_USE_DEFAULT_PPQN)
 Principal constructor.
- virtual ∼seqedit ()

A rote destructor.

Private Member Functions

void set zoom (int zoom)

Selects the given zoom value.

void set snap (int snap)

Selects the given snap value, which is the number of ticks in a snap-sized interval.

void set_note_length (int note_length)

Selects the given note-length value.

void set beats per bar (int bpm)

Set the bpm (beats per measure) value, using the given parameter, and some internal values passed to apply_\leftarrow length().

void set beat width (int bw)

Set the bw (beat width) value, using the given parameter, and some internal values passed to apply length().

void set rec vol (int recvol)

Passes the given parameter to sequence::set_rec_vol().

void horizontal_adjust (double step)

This function provides optimization for the on_scroll_event() function.

void vertical_adjust (double step)

This function provides optimization for the on_scroll_event() function.

void horizontal_set (double value)

Sets the exact position of a horizontal scroll-bar.

void vertical_set (double value)

Sets the exact position of a vertical scroll-bar.

• void set_measures (int lim)

Set the measures value, using the given parameter, and some internal values passed to apply_length().

• void apply_length (int bpm, int bw, int measures)

Sets the sequence length based on the three given parameters.

• long get_measures ()

Calculates the measures value based on the bpm (beats per measure), ppqn (parts per quarter note), and bw (beat width) values, and returns the resultant measures value.

• void set midi channel (int midichannel)

Selects the given MIDI channel parameter in the main sequence object, so that it will use that channel.

· void set_midi_bus (int midibus)

Selects the given MIDI buss parameter in the main sequence object, so that it will use that buss.

void set scale (int scale)

Selects the given scale value.

· void set key (int note)

Selects the given key (signature) value.

void set_background_sequence (int seq)

Draws the given background sequence on the Pattern editor so that the musician has something to see that can be played against.

void name_change_callback ()

Set the name for the main sequence to this object's entry name.

void play_change_callback ()

Passes the play status to the sequence object.

• void record_change_callback ()

Passes the recording status to the sequence object.

void q_rec_change_callback ()

Passes the quantized-recording status to the sequence object.

• void thru change callback ()

Passes the MIDI Thru status to the sequence object.

• void undo callback ()

Pops an undo operation from the sequence object, and then tells the segroll, seqtime, seqdata, and seqevent objects to redraw.

void redo callback ()

Pops a redo operation from the sequence object, and then tell the segroll, seqtime, seqdata, and seqevent objects to redraw.

void set_data_type (midibyte status, midibyte control=0)

Sets the data type based on the given parameters.

- void update_all_windows ()
- void fill top bar ()

This function inserts the user-interface items into the top bar or panel of the pattern editor; this bar has two rows of user interface elements.

• void create menus ()

Creates the various menus by pushing menu elements into the menus.

void popup_menu (Gtk::Menu *menu)

Pops up the given pop-up menu.

void popup_event_menu ()

Populates the event-selection menu that drops from the "Event" button in the bottom row of the Pattern editor.

· void popup midibus menu ()

Populates the MIDI Output buss pop-up menu.

• void popup_sequence_menu ()

Populates the "set background sequence" menu (drops from the button that has some note-bars on it at the right of the second row of the top bar).

void popup_tool_menu ()

Sets up the pop-up menus that are brought up by pressing the Tools button, which shows a hammer image.

void popup_midich_menu ()

Populates the MIDI Channel pop-up menu.

• Gtk::Image * create_menu_image (bool state=false)

Sets the menu pixmap depending on the given state, where true is a full menu (black backgroun), and empty menu (gray background).

• bool timeout ()

Update the window after a time out, based on dirtiness and on playback progress.

• void do action (int action, int var)

Implements the actions brought forth from the Tools (hammer) button.

- void mouse_action (mouse_action_e action)
- void change_focus (bool set_it=true)

Changes what perform and mainwid see as the "current sequence".

void handle_close ()

Handles closing the sequence editor.

• void on_realize ()

On realization, calls the base-class version, and connects the redraw timeout signal, timed at redraw_period_ms().

void on_set_focus (Widget *focus)

On receiving focus, attempt to tell mainwid that this sequence is now the current sequence.

bool on focus in event (GdkEventFocus *)

Implements the on-focus event handling.

bool on_focus_out_event (GdkEventFocus *)

Implements the on-unfocus event handling.

bool on delete event (GdkEventAny *event)

Handles an on-delete event.

bool on_scroll_event (GdkEventScroll *ev)

Handles an on-scroll event.

bool on_key_press_event (GdkEventKey *ev)

Handles a key-press event.

Private Attributes

- friend segmenu
- · const int m_initial_zoom

Provides the initial zoom, used for restoring the original zoom using the 0 key.

• int m zoom

Provides the zoom values: 1 2 3 4, and 1, 2, 4, 8, 16.

• int m snap

Used in setting the snap-to value in pulses, of f = 1.

• int m_note_length

The default length of a note to be inserted by a right-left-click operation.

• int m_scale

Setting for the music scale, can now be saved with the sequence.

int m_key

Setting for the music key, can now be saved with the sequence.

· int m bgsequence

Setting for the background sequence, can now be saved with the sequence.

long m_measures

Provides the length of the sequence in measures.

• int m_ppqn

Holds a copy of the current PPQN for the sequence (and the entire MIDI file).

• sequence & m_seq

Holds a reference to the sequence that this window represents.

• Gtk::MenuBar * m menubar

A number of user-interface objects for common.

Gtk::Menu * m_menu_tools

The "hammer" tool button menu.

• Gtk::Menu * m_menu_zoom

Magnifying glass zoom menu.

Gtk::Menu * m_menu_snap

Two-arrows grid-snap menu.

• Gtk::Menu * m_menu_note_length

Notes menu for note length.

• Gtk::Menu * m_menu_length

Pattern-length "bars" menu.

• Gtk::Menu * m_menu_midich

MIDI channel DIN menu button.

• Gtk::Menu * m menu midibus

MIDI output buss menu button.

Gtk::Menu * m_menu_data

"Event" button to select data.

• Gtk::Menu * m menu key

"Music key" menu button.

Gtk::Menu * m_menu_scale

"Music scale" menu button.

• Gtk::Menu * m_menu_sequences

"Background sequence" button.

• Gtk::Menu * m_menu_bpm

Beats/measure numerator menu.

Gtk::Menu * m_menu_bw

Beat-width denominator menu.

```
• Gtk::Menu * m_menu_rec_vol
      Recording level "Vol" button.

    Gtk::Adjustment * m vadjust

      Scrollbar and adjustment objects for horizontal and vertical panning.

    Gtk::Adjustment * m_hadjust

     Horizontal motion scratchpad.
• Gtk::VScrollbar * m_vscroll_new
      Main vertical scroll-bar.

    Gtk::HScrollbar * m hscroll new

     Main horizontal scroll-bar.
• segkeys * m segkeys wid
      Handles the piano-keys part of the pattern-editor user-interface.

    seqtime * m_seqtime_wid

      Handles the time-line (bar or measures) part of the pattern-editor user-interface.

    seqdata * m seqdata wid

      Handles the event-data part of the pattern-editor user-interface.
seqevent * m_seqevent_wid
     Handles the small event part of the pattern-editor user-interface, where events can be moved and added.
seqroll * m_seqroll_wid
     Handles the piano-roll part of the pattern-editor user-interface.
• Gtk::Table * m table
     More user-interface elements.

    Gtk::VBox * m vbox

     Layout box for 3 h-boxes.

    Gtk::HBox * m_hbox

      Topmost menu/text dialog row.
• Gtk::HBox * m hbox2
      Second row of buttons.
• Gtk::Button * m_button_undo
      Undo-edit button.
• Gtk::Button * m_button_redo
      Redo-edit button.
• Gtk::Button * m_button_quantize
      Quantize-pattern button.
• Gtk::Button * m button tools
      Button for the Tools menu.
• Gtk::Button * m button sequence
      Button for Background pattern.

    Gtk::Entry * m_entry_sequence

      Text for background pattern.

    Gtk::Button * m button bus

      Button for MIDI Buss menu.
• Gtk::Entry * m_entry_bus
      Text showing MIDI Buss name.
• Gtk::Button * m button channel
      Button for the MIDI Channel.
• Gtk::Entry * m_entry_channel
      Text for the MIDI Channel.

    Gtk::Button * m button snap

      Button for the Grid-snap menu.

    Gtk::Entry * m_entry_snap
```

```
12.61 seq64::seqedit Class Reference
          Text for selected Grid-snap.
    • Gtk::Button * m_button_note_length
          Button for Note-length menu.

    Gtk::Entry * m_entry_note_length

          Text showing the Note-length.
    • Gtk::Button * m button zoom
          Button for the Zoom menu.
    • Gtk::Entry * m_entry_zoom
          Text for the selected Zoom.
    • Gtk::Button * m_button_length
          Button for pattern-length.
    • Gtk::Entry * m_entry_length
          Text for the pattern-length.

    Gtk::Button * m button key

          Button for the Music Key.

    Gtk::Entry * m_entry_key

          Text for selected Music Key.
    • Gtk::Button * m button scale
          Button for the Music Scale.
    • Gtk::Entry * m_entry_scale
          Text for the Music Scale.
    • Gtk::Tooltips * m_tooltips
          Tooltip collector for dialog.
    • Gtk::Button * m button data
          Button for Event (data) menu.
    • Gtk::Entry * m_entry_data
          Text for the selected Event.
    • Gtk::Button * m_button_bpm
          Button for Beats/Measure menu.
```

Gtk::Entry * m_entry_bpm Text for chosen Beats/Measure.

• Gtk::Button * m button bw

Button for Beat-Width menu.

Gtk::Entry * m_entry_bw

Text for chosen Beat-Width.

• Gtk::Button * m_button_rec_vol

Button for recording volume.

Gtk::ToggleButton * m_toggle_play

Pattern-to-MIDI record button.

• Gtk::ToggleButton * m_toggle_record

MIDI-port-to-pattern button.

Gtk::ToggleButton * m_toggle_q_rec

Quantized-record MIDI button.

Gtk::ToggleButton * m_toggle_thru

MIDI-to-pattern-MIDI button.

• Gtk::Entry * m_entry_name

Name of the sequence.

midibyte m_editing_status

Indicates what MIDI event/status the data window currently editing.

• midibyte m_editing_cc

Indicates what MIDI CC value the data window currently editing.

bool m have focus

Indicates that the focus has already been changed to this sequence.

Static Private Attributes

- static int m_initial_snap
 Static data members.
- static int m_initial_note_length

Additional Inherited Members

12.61.1 Detailed Description

- · perform
- · segroll
- · seqkeys
- · segdata
- · segtime
- · seqevent
- · sequence

This class has a metric ton of user-interface objects and other members.

12.61.2 Constructor & Destructor Documentation

```
12.61.2.1 seq64::seqedit::seqedit ( perform & p, sequence & seq, int pos, int ppqn = SEQ64_USE_DEFAULT_PPQN )
```

If provided, override the scale, key, and background-sequence with the values stored in the file with the sequence, if they are set to non-default values. This is a new feature.

Todo Offload most of the work into an initialization function like options does.

Todo Support the hightlight feature in one or both perfedit windows in the same way it is done in the mainwid.

Horizontal Gtk::Adjustment constructor: The initial value was 0 on a range from 0 to 1, with step and page increments of 1, and a page_size of 1. We can fix these values here, or create an h_adjustment() function similar to eventedit ::v_adjustment(), which first gets called in on_realize().

```
12.61.2.2 seq64::seqedit::~seqedit() [virtual]
```

12.61.3 Member Function Documentation

```
12.61.3.1 void seq64::seqedit::set_zoom(int z) [private]
```

It is passed to the seqroll, seqtime, seqdata, and seqevent objects, as well. This function doesn't check if the zoom will change, because this function might be used to initialize the zoom of the children.

The notation for zoom in the user-interface is in pixels:ticks, but I would prefer to use pulses/pixel (pulses per pixel). Oh well. Note that this value of zoom is saved to the "user" configuration file when Sequencer64 exit.

Parameters

z The prospective zoom value to set. It is applied only if between the minimum and maximum allowed zoom values, inclusive. See the usr().min_zoom() and usr().max_zoom() function.

```
12.61.3.2 void seq64::seqedit::set_snap ( int s ) [private]
```

It is passed to the seqroll, seqevent, and sequence objects, as well.

The default initial snap is the default PPQN divided by 4, or the equivalent of a 16th note (48 ticks). The snap divisor is 192 * 4 / 48 or 16.

Parameters

The prospective snap value to set. It is checked only to make sure it is greater than 0, to avoid a numeric exception.

```
12.61.3.3 void seq64::seqedit::set_note_length ( int notelength ) [private]
```

It is passed to the seqroll object, as well.

Warning

Currently, we don't handle changes in the global PPQN after the creation of the menu. The creation of the menu hard-wires the values of note-length. To adjust for a new global PQN, we will need to store the original PPQN (m_original_ppqn = m_ppqn), and then adjust the notelength based on the new PPQN. For example if the new PPQN is twice as high as 192, then the notelength should double, though the text displayed in the "Note length" field should remain the same. However, we do adjust for a non-default PPQN at startup time.

Parameters

```
12.61.3.4 void seq64::seqedit::set_beats_per_bar( int bpm ) [private]
```

12.61.3.5 void seq64::seqedit::set_beat_width(int bw) [private]

12.61.3.6 void seq64::seqedit::set_rec_vol(int recvol) [inline], [private]

Parameters

recvol The setting to be made, obtained from the recording-volume ("Vol") menu.

12.61.3.7 void seq64::seqedit::horizontal_adjust(double step) [inline], [private]

A duplicate of the one in segroll.

Parameters

step	Provides the step value to use for adjusting the horizontal scrollbar. See		
	gui_drawingarea_gtk2::scroll_hadjust() for more information.		

12.61.3.8 void seq64::seqedit::vertical_adjust(double step) [inline], [private]

A near-duplicate of the one in seqroll.

Parameters

step Provides the step value to use for adjusting the vertical scrollbar. See gui_drawingarea_gtk2::scroll_vadjust() for more information.

12.61.3.9 void seq64::seqedit::horizontal_set(double value) [inline], [private]

Parameters

value The desired position. Mostly this is either 0.0 or 9999999.0 (an "infinite" value to select the start or end position.

12.61.3.10 void seq64::seqedit::vertical_set(double value) [inline], [private]

Parameters

value	The desired position. Mostly this is either 0.0 or 9999999.0 (an "infinite" value to select the start or			
	position.			

12.61.3.11 void seq64::seqedit::set_measures(int lim) [private]

Parameters

lim Provides the sequence length, in measures.

12.61.3.12 void seq64::seqedit::apply_length (int bpm, int bw, int measures) [private]

There's an implicit "adjust-triggers = true" parameter used in sequence::set_length().

Then the seqroll, seqtime, seqdata, and seqevent objects are reset().

```
12.61.3.13 long seq64::seqedit::get_measures( ) [private]
```

Todo Create a sequence::set_units() function or a sequence::get_measures() function to forward to.

```
12.61.3.14 void seg64::segedit::set_midi_channel(int midichannel) [private]
```

Should this change set the is-modified flag? Where should validation occur?

```
12.61.3.15 void seq64::seqedit::set_midi_bus(int bus) [private]
```

Should this change set the is-modified flag? Where should validation against the ALSA or JACK buss limits occur?

Also, it would be nice to be able to update this display of the MIDI bus in the field if we set it from the segmenu.

```
12.61.3.16 void seq64::seqedit::set_scale ( int scale ) [private]
```

It is passed to the sequence, so that it can be saved as part of the sequence data.

Note that the "initial value" for this parameter is a static variable that gets set to the new value, so that opening up another sequence causes the sequence to take on the new "initial value" as well. A feature, but should it be optional? Now it is, based on the setting of usr().global_seq_feature().

```
12.61.3.17 void seq64::seqedit::set_key ( int key ) [private]
```

It is passed to the sequence, so that it can be saved as part of the sequence data.

Note that the "initial value" for this parameter is a static variable that gets set to the new value, so that opening up another sequence causes the sequence to take on the new "initial value" as well. A feature, but should it be optional? Now it is, based on the setting of usr().global_seq_feature().

```
12.61.3.18 void seq64::seqedit::set_background_sequence(int seqnum) [private]
```

As a new feature, it is also passed to the sequence, so that it can be saved as part of the sequence data, but only if less or equal to the maximum single-byte MIDI value, 127.

Note that the "initial value" for this parameter is a static variable that gets set to the new value, so that opening up another sequence causes the sequence to take on the new "initial value" as well. A feature, but should it be optional? Now it is, based on the setting of usr().global_seq_feature().

```
12.61.3.19 void seq64::seqedit::name_change_callback( ) [private]
```

That name is the name the user has given to the sequence being edited.

```
12.61.3.20 void seq64::seqedit::play_change_callback( ) [private]
12.61.3.21 void seq64::seqedit::record_change_callback( ) [private]
Stazed:
 Both record_change_callback() and thru_change_callback() will call
 set_sequence_input() for the same sequence. We only need to call it if
 it is not already set, if setting. And, we should not unset it if the
 m_toggle_thru->get_active() is true.
12.61.3.22 void seq64::seqedit::q_rec_change_callback( ) [private]
12.61.3.23 void seq64::seqedit::thru_change_callback( ) [private]
Stazed:
 Both record_change_callback() and thru_change_callback() will call
 set_sequence_input() for the same sequence. We only need to call it if
 it is not already set, if setting. And, we should not unset it if the
 m_toggle_thru->get_active() is true.
12.61.3.24 void seq64::seqedit::undo_callback( ) [private]
12.61.3.25 void seq64::seqedit::redo_callback( ) [private]
12.61.3.26 void seq64::seqedit::set data type ( midibyte status, midibyte control = 0 ) [private]
```

This function uses the hardwired array c_controller_names.

Parameters

status	The current editing status.
control	The control value. However, we really need to validate it!

```
12.61.3.27 void seq64::seqedit::update_all_windows( ) [private]
12.61.3.28 void seq64::seqedit::fill_top_bar( ) [private]
```

Note that, if a non-default title for the sequence is in force, then we immediately force the focus to the sequol "widget", so that the space bar can be used to control playback, instead of immediately erasing the name of the sequence. The following commented radio-buttons were a visual way to select the modes of note editing (select, draw, and grow). These can easily be done with the left mouse button, keystrokes, or some other tricks, though.

```
12.61.3.29 void seq64::seqedit::create_menus() [private]
```

The first menu is the Zoom menu, represented in the pattern/sequence editor by a button with a magnifying glass. The values are "pixels to ticks", where "ticks" are actually the "pulses" of "pulses per quarter note". We would prefer the notation "n" instead of "1:n", as in "n pulses per pixel".

Note that many of the setups here could be loops through data structures. The Snap menu is actually the Grid Snap button, which shows two arrows pointing to a central bar. This menu somewhat duplicates the same menu in perfedit.

This menu lets one set the key of the sequence, and is brought up by the button with the "golden key" image on it.

This button shows a down around for the bottom half of the time signature. It's tooltip is "Time signature. Length of beat." But it is called bw, or beat width, in the code.

This menu is shown when pressing the button at the bottom of the window that has "Vol" as its label. Let's show the numbers as well to help the user. And we'll have to document this change.

This menu sets the scale to show on the panel, and the button shows a "staircase" image. See the c_music_scales enumeration defined in the globals module.

This section sets up two different menus. The first is m_menu_length. This menu lets one set the sequence length in bars. The second menu is the m_menu_bpm, or BPM, which here means "beats per measure" (not "beats per minute").

```
12.61.3.30 void seq64::seqedit::popup_menu ( Gtk::Menu * menu ) [private]
12.61.3.31 void seq64::seqedit::popup_event_menu ( ) [private]
```

This menu has a large number of items. I think they are filled in in code, but can also be loaded from \sim /.seq24usr. To be determined. Create the 8 sub-menus for the various ranges of controller changes, shown 16 per sub-menu.

```
12.61.3.32 void seg64::segedit::popup_midibus_menu() [private]
```

The MIDI busses are obtained by getting the mastermidibus object, and iterating through the busses that it contains.

```
12.61.3.33 void seq64::seqedit::popup_sequence_menu( ) [private]
```

It is populated with an "Off" menu entry, and a second "[0]" menu entry that pulls up a drop-down menu of all of the patterns/sequences that are present in the MIDI file for screen-set 0. If more screensets have active sequences, then their screen-set number appears in the screen-set section of the menu.

Now, at present, we can only save background sequence numbers that are less than 128, which means the sequences from 0 to 127, or the first four screen sets. Higher sequences can be selected, but, right now, they cannot be saved. We'll probably fix that at some point, low priority.

```
12.61.3.34 void seq64::seqedit::popup_tool_menu( ) [private]
```

This button shows three sub-menus that need to be filled in by this function. All the functions accessed here seem to be implemented by the do_action() function.

```
12.61.3.35 void seq64::seqedit::popup_midich_menu() [private]
12.61.3.36 Gtk::Image * seq64::seqedit::create_menu_image(bool state = false) [private]
12.61.3.37 bool seq64::seqedit::timeout() [private]
```

Note the new call to seqroll::follow_progress(). This allows the seqroll to pop to the next frame of events to continue to show the moving progress bar. Does this need to be an option? It only affects patterns longer than a measure or two, whatever the width of the seqroll window is. This is a new feature that is not in seq24.

What about seqtime? That doesn't change.

```
12.61.3.38 void seq64::seqedit::do_action ( int action, int var ) [private]
```

Note that the push_undo() calls push all of the current events (in sequence::m_events) onto the stack (as a single entry).

```
12.61.3.39 void seq64::seqedit::mouse_action( mouse_action_e action ) [private]
12.61.3.40 void seq64::seqedit::change_focus( bool set_it = true ) [private]
```

Similar to the same function in eventedit.

Parameters

set⊷	If true (the default value), indicates we want focus, otherwise we want to give up focus.
_it	

```
12.61.3.41 void seq64::seqedit::handle_close() [private]

12.61.3.42 void seq64::seqedit::on_realize() [private]

12.61.3.43 void seq64::seqedit::on_set_focus(Widget*focus) [private]

Only works in certain circumstances.

12.61.3.44 bool seq64::seqedit::on_focus_in_event(GdkEventFocus*) [private]

12.61.3.45 bool seq64::seqedit::on_focus_out_event(GdkEventFocus*) [private]

12.61.3.46 bool seq64::seqedit::on_delete_event(GdkEventAny*event) [private]
```

It tells the sequence to stop recording, tells the perform object's mastermidibus to stop processing input, and sets the sequence object's editing flag to false.

Warning

This function also calls "delete this"!

Returns

Always returns false.

```
12.61.3.47 bool seq64::seqedit::on_scroll_event( GdkEventScroll * ev ) [private]
```

This handles moving the scroll wheel on a mouse or do a two-fingered scrolling action on a touchpad. If no modifier key is pressed, this moves the view up or down on the "notes" coordinate, showing different piano keys. This behavior is implemented in seqkeys::on_scroll_event(), and is called into play by returning false here.

If the Ctrl key is pressed, then the scrolling action causes the view to zoom in or out. This behavior is implemented here.

If the Shift key is pressed, then the scrolling action moves the view horizontally on the time-line (measures-line) of the piano roll. This behavior is implemented here.

```
12.61.3.48 bool seq64::seqedit::on_key_press_event ( GdkEventKey * ev ) [private]
```

A number of new keystrokes are processed, so that we can lessen the reliance on the mouse and work a little faster.

```
- Ctrl-W keypress. This keypress closes the sequence/pattern editor
window by way of calling on_delete_event(). We could apply this
convention to all the other windows.
```

- z 0 Z zoom keys. "z" zooms out, "Z" (Shift-z) zooms in, and "0" resets the zoom to the default.
- Page-Up and Page-Down. Moves up and down in the piano roll.
- Home and End. Page to the top or the bottom of the piano roll.
- Shift-Page-Up and Shift-Page-Down. Move left and right in the piano roll.
- Shift-Home and Shift-End. Page to the start or the end of the piano roll.
- Ctrl-Page-Up and Ctrl-Page-Down. Mirrors the zoom-in and zoom-out capabilities of scrolling up and down with the mouse while the Ctrl key is pressed.

The Keypad-End key is an issue on our ASUS "gaming" laptop. Whether it is seen as a "1" or an "End" key depends on an interaction between the Shift and the Num Lock key. Annoying, takes some time to get used to.

Parameters

ev Provides the keystroke event to be handled.

Returns

Returns true if we handled the keystroke here. Otherwise, returns the value of Gtk::Window::on_key_press-_event(ev).

12.61.4 Field Documentation

```
12.61.4.1 friend seq64::seqedit::seqmenu [private]
12.61.4.2 int seq64::seqedit::m_initial_snap [static], [private]
```

These items apply to all of the instances of seqedit, and are passed on to the following constructors:

- segdata
- · segevent
- · segroll
- · seqtime

The snap and note-length defaults would be good to write to the "user" configuration file. The scale and key would be nice to write to the proprietary section of the MIDI song. Or, even more flexibly, to each sequence, if that makes sense to do, since all tracks would generally be in the same key. Right, Charles Ives?

Note that, currently, that some of these "initial values" are modified, so that they are "contagious". That is, the next sequence to be opened in the sequence editor will adopt these values. This is a long-standing feature of Seq24, but strikes us as a bit surprising.

Change Note ca 2016-04-10 If we just double the PPQN, then the snap divisor becomes 32, and the snap interval is a 32nd note. We would like to keep it at a 16th note. We correct the snap ticks to the actual PPQN ratio.

```
12.61.4.3 int seq64::seqedit::m_initial_note_length [static], [private]

12.61.4.4 const int seq64::seqedit::m_initial_zoom [private]

12.61.4.5 int seq64::seqedit::m_zoom [private]
```

The value of zoom is the same as the number of pixels per tick on the piano roll.

```
12.61.4.6 int seq64::seqedit::m_snap [private]

12.61.4.7 int seq64::seqedit::m_note_length [private]

12.61.4.8 int seq64::seqedit::m_scale [private]

12.61.4.9 int seq64::seqedit::m_key [private]

12.61.4.10 int seq64::seqedit::m_bgsequence [private]

12.61.4.11 long seq64::seqedit::m_measures [private]

12.61.4.12 int seq64::seqedit::m_ppqn [private]

12.61.4.13 sequence& seq64::seqedit::m_seq [private]

12.61.4.14 Gtk::MenuBar* seq64::seqedit::m_menubar [private]
```

Many of these are menu items, and are associated with buttons that, when pressed, bring up the menu for display and selection of its entries. The top bar with menu buttons.

```
12.61.4.15 Gtk::Menu* seq64::seqedit::m_menu_tools [private]
12.61.4.16 Gtk::Menu* seq64::seqedit::m_menu_zoom [private]
12.61.4.17 Gtk::Menu* seq64::seqedit::m_menu_snap [private]
12.61.4.18 Gtk::Menu* seq64::seqedit::m_menu_note_length [private]
12.61.4.19 Gtk::Menu* seq64::seqedit::m_menu_length [private]
12.61.4.20 Gtk::Menu* seq64::seqedit::m_menu_midich [private]
12.61.4.21 Gtk::Menu* seq64::seqedit::m_menu_midibus [private]
12.61.4.22 Gtk::Menu* seq64::seqedit::m_menu_data [private]
12.61.4.23 Gtk::Menu* seq64::seqedit::m_menu_key [private]
12.61.4.24 Gtk::Menu* seq64::seqedit::m_menu_scale [private]
12.61.4.25 Gtk::Menu* seq64::seqedit::m_menu_sequences [private]
12.61.4.26 Gtk::Menu* seq64::seqedit::m_menu_bpm [private]
12.61.4.27 Gtk::Menu* seq64::seqedit::m_menu_bw [private]
12.61.4.28 Gtk::Menu* seq64::seqedit::m_menu_rec_vol [private]
12.61.4.29 Gtk::Adjustment* seq64::seqedit::m_vadjust [private]
Vertical position descriptor.
12.61.4.30 Gtk::Adjustment* seq64::seqedit::m_hadjust [private]
12.61.4.31 Gtk::VScrollbar* seq64::seqedit::m_vscroll_new [private]
12.61.4.32 Gtk::HScrollbar* seq64::seqedit::m_hscroll_new [private]
12.61.4.33 seqkeys* seq64::seqedit::m_seqkeys_wid [private]
This item draws the piano-keys at the left of the seqedit window.
12.61.4.34 seqtime* seq64::seqedit::m_seqtime_wid [private]
```

This is the location where the measure numbers and the END marker are shown.

```
12.61.4.35 seqdata* seq64::seqedit::m_seqdata_wid [private]
```

This is the area at the bottom of the window that shows value lines for the selected kinds of events.

These items provide a number of buttons and text-entry fields, as well as their layout. The layout table for editor.

```
12.61.4.39 Gtk::VBox* seq64::seqedit::m_vbox [private]
12.61.4.40 Gtk::HBox* seq64::seqedit::m_hbox [private]
12.61.4.41 Gtk::HBox* seq64::seqedit::m_hbox2 [private]
12.61.4.42 Gtk::Button* seg64::segedit::m button undo [private]
12.61.4.43 Gtk::Button* seq64::seqedit::m_button_redo [private]
12.61.4.44 Gtk::Button* seq64::seqedit::m_button_quantize [private]
12.61.4.45 Gtk::Button* seq64::seqedit::m_button_tools [private]
12.61.4.46 Gtk::Button* seq64::seqedit::m_button_sequence [private]
12.61.4.47 Gtk::Entry* seq64::seqedit::m_entry_sequence [private]
12.61.4.48 Gtk::Button* seq64::seqedit::m_button_bus [private]
12.61.4.49 Gtk::Entry* seq64::seqedit::m_entry_bus [private]
12.61.4.50 Gtk::Button* seq64::seqedit::m_button_channel [private]
12.61.4.51 Gtk::Entry* seq64::seqedit::m_entry_channel [private]
12.61.4.52 Gtk::Button* seq64::seqedit::m_button_snap [private]
12.61.4.53 Gtk::Entry* seq64::seqedit::m_entry_snap [private]
12.61.4.54 Gtk::Button* seq64::seqedit::m_button_note_length [private]
```

```
12.61.4.55 Gtk::Entry* seq64::seqedit::m_entry_note_length [private]
12.61.4.56 Gtk::Button* seq64::seqedit::m_button_zoom [private]
12.61.4.57 Gtk::Entry* seq64::seqedit::m_entry_zoom [private]
12.61.4.58 Gtk::Button* seq64::seqedit::m_button_length [private]
12.61.4.59 Gtk::Entry* seq64::seqedit::m_entry_length [private]
12.61.4.60 Gtk::Button* seq64::seqedit::m_button_key [private]
12.61.4.61 Gtk::Entry* seq64::seqedit::m_entry_key [private]
12.61.4.62 Gtk::Button* seq64::seqedit::m_button_scale [private]
12.61.4.63 Gtk::Entry* seq64::seqedit::m_entry_scale [private]
12.61.4.64 Gtk::Tooltips* seq64::seqedit::m_tooltips [private]
12.61.4.65 Gtk::Button* seq64::seqedit::m_button_data [private]
12.61.4.66 Gtk::Entry* seq64::seqedit::m_entry_data [private]
12.61.4.67 Gtk::Button* seq64::seqedit::m_button_bpm [private]
12.61.4.68 Gtk::Entry* seq64::seqedit::m_entry_bpm [private]
12.61.4.69 Gtk::Button* seq64::seqedit::m_button_bw [private]
12.61.4.70 Gtk::Entry* seq64::seqedit::m_entry_bw [private]
12.61.4.71 Gtk::Button* seq64::seqedit::m_button_rec_vol [private]
12.61.4.72 Gtk::ToggleButton* seq64::seqedit::m_toggle_play [private]
12.61.4.73 Gtk::ToggleButton* seq64::seqedit::m_toggle_record [private]
12.61.4.74 Gtk::ToggleButton* seq64::seqedit::m_toggle_q_rec [private]
12.61.4.75 Gtk::ToggleButton* seq64::seqedit::m_toggle_thru [private]
12.61.4.76 Gtk::Entry* seq64::seqedit::m_entry_name [private]
12.61.4.77 midibyte seq64::seqedit::m_editing_status [private]
```

12.61.4.78 midibyte seq64::seqedit::m_editing_cc [private]

12.61.4.79 bool seq64::seqedit::m_have_focus [private]

12.62 seq64::seqevent Class Reference

Implements the piano event drawing area.

Inheritance diagram for seq64::seqevent:



Public Member Functions

seqevent (perform &p, sequence &seq, int zoom, int snap, seqdata &seqdata_wid, Gtk::Adjustment &hadjust, int ppqn=SEQ64_USE_DEFAULT_PPQN)

Principal constructor.

virtual ∼seqevent ()

Let's provide a do-nothing virtual destructor.

· void reset ()

This function basically resets the whole widget as if it was realized again.

void redraw ()

Adjusts the scrolling offset for ticks, updates the pixmap, and draws it on the window.

void set zoom (int zoom)

Sets zoom to the given value, and resets if the value ended up being changed.

void set_snap (int snap)

'Setter' function for member m snap Simply sets the snap member.

void set_data_type (midibyte status, midibyte control)

Sets the status to the given parameter, and the CC value to the given optional control parameter, which defaults to 0.

void update sizes ()

If the window is realized, this function creates a pixmap with window dimensions, the updates the pixmap, and queues up a redraw.

void draw_background ()

This function updates the background.

void draw_events_on_pixmap ()

This function fills the main pixmap with events.

void draw_pixmap_on_window ()

This function currently just queues up a draw operation for the pixmap.

void draw_selection_on_window ()

Draw the selected events on the window.

void update_pixmap ()

Redraws the background pixmap on the main pixmap, then puts the events on.

Private Member Functions

virtual void force_draw ()

Forces a draw on the current drawable area of the window.

int idle_redraw ()

Implements redraw while idling.

void x to w (int x1, int x2, int &x, int &w)

This function checks the mins / maxes.

void drop_event (midipulse tick)

Drops (adds) an event at the given tick.

void draw_events_on (Glib::RefPtr< Gdk::Drawable > draw)

Draws events on the given drawable object.

void start paste ()

Starts a paste operation.

void change_horz ()

Changes the horizontal scrolling offset for ticks, then updates the pixmap and forces a redraw.

void convert_x (int x, midipulse &tick)

Takes the screen x coordinate, multiplies it by the current zoom, and returns the tick value in the given parameter.

• void convert_t (midipulse tick, int &x)

Converts the given tick value to an x corrdinate, based on the zoom, and returns it via the second parameter.

void snap_y (int &y)

This function performs a 'snap' on y.

void snap_x (int &x)

This function performs a 'snap' on x.

• void on_realize ()

Implements the on-realize callback.

bool on_expose_event (GdkEventExpose *ev)

Implements the on-expose event callback.

bool on_button_press_event (GdkEventButton *ev)

Implements the on-button-press event callback.

bool on button release event (GdkEventButton *ev)

Implements the on-button-release event callback.

bool on_motion_notify_event (GdkEventMotion *ev)

Implements the on-motion-notify event callback.

bool on_focus_in_event (GdkEventFocus *)

Responds to a focus event by setting the HAS_FOCUS flag.

• bool on_focus_out_event (GdkEventFocus *)

Responds to a unfocus event by resetting the HAS_FOCUS flag.

bool on_key_press_event (GdkEventKey *p0)

Implements the key-press event callback function.

void on size allocate (Gtk::Allocation &)

Implements the on-size-allocate event callback.

Private Attributes

• FruitySeqEventInput m_fruity_interaction

Provides the mouse-handling paradigm for the fruity interaction.

Seq24SeqEventInput m_seq24_interaction

Provides the normal mouse-handling for Sequencer64.

sequence & m_seq

Provides a reference to the sequence whose data is represented in this sequent object.

• int m_zoom

Zoom setting, means that one pixel == m_zoom ticks.

• int m_snap

The grid-snap setting for the event bar grid.

• int m_ppqn

The value to use for the PPQN for this sequence.

• GdkRectangle m old

Used in drawing the event selection in the thing event row.

• GdkRectangle m_selected

Used in moving and pasting the selected events in the thin event row.

· int m scroll offset ticks

Provides the offset of the ticks in the event view based on where the scroll-bar has moved the view "window".

int m_scroll_offset_x

Provides the offset of the pixels in the event view based on where the scroll-bar has moved the view "window".

· segdata & m segdata wid

The data view that parallels this event view.

bool m selecting

Used when highlighting a bunch of events.

bool m_moving_init

Used externally by the fruityseq and seq24seq modules, to initialize the act of moving events.

· bool m_moving

Indicates that this pane is in the act of moving a selection.

bool m_growing

Used externally by the fruityseq and seq24seq modules, when growing the event duration.

bool m painting

Used externally by the fruityseq and seq24seq modules, in painting the selected events.

bool m_paste

Indicates that we've selected some events and are in paste mode.

• int m_move_snap_offset_x

Used externally by the fruityseq and seq24seq modules, in snapping.

• midibyte m_status

Indicates what is the data window currently editing.

• midibyte m_cc

Indicates what is the data window currently editing.

Friends

- struct FruitySeqEventInput
- struct Seq24SeqEventInput

Additional Inherited Members

12.62.1 Constructor & Destructor Documentation

12.62.1.1 seq64::seqevent::seqevent (perform & p, sequence & seq, int zoom, int snap, seqdata & seqdata_wid, Gtk::Adjustment & hadjust, int ppqn = SEQ64_USE_DEFAULT_PPQN)

Parameters

p	The "parent" perform object controlling all of the sequences.
seq	The current sequence operated on by this object.
zoom	The initial zoom value.
snap	The initial snap value.
seqdata_wid	The data pane that this event pane is associated with.
hadjust	The horizontal scroll-bar.
ppqn	The initial PPQN value.

12.62.1.2 virtual seq64::seqevent::~seqevent() [inline], [virtual]

12.62.2 Member Function Documentation

12.62.2.1 void seq64::seqevent::reset ()

Basically identical to seqtime::reset().

```
12.62.2.2 void seq64::seqevent::redraw ( )
```

Somewhat similar to segroll::redraw().

12.62.2.3 void seq64::seqevent::set_zoom (int z)

Parameters

|z| The desired zoom value, presumably already validated by the caller.

```
12.62.2.4 void seq64::seqevent::set_snap ( int snap ) [inline]
```

The parameter is not validated.

12.62.2.5 void seq64::seqevent::set_data_type (midibyte status, midibyte control)

Then redraws.

Parameters

status	The status/event byte to set. For example, EVENT_NOTE_ON and EVENT_NOTE off. This byte should have the channel nybble cleared.
control	The MIDI CC byte to set.

```
12.62.2.6 void seq64::seqevent::update_sizes ( )
```

This ends up filling the background with dotted lines, etc.

```
12.62.2.7 void seq64::seqevent::draw_background()
```

It sets the foreground to white, draws the rectangle, in order to clear the pixmap. The build-time option SEQ64← _SOLID_PIANOROLL_GRID causes solid lines to be drawn, in gray, instead of dotted black lines, for a smoother look.

Also, as a trial option, if the current data type is EVENT_NOTE_ON, EVENT_NOTE_OFF, and EVENT_AFTER

TOUCH, we draw the background in light grey to remind the user that there are issues in copying or moving these events around (unlinked) by themselves.

```
12.62.2.8 void seq64::seqevent::draw_events_on_pixmap( )
```

12.62.2.9 void seq64::seqevent::draw_pixmap_on_window()

Old comments:

It then tells event to do the same. We changed something on this window, and chances are we need to update the event widget as well and update our velocity window.

```
12.62.2.10 void seq64::seqevent::draw_selection_on_window( )
```

12.62.2.11 void seq64::seqevent::update_pixmap ()

12.62.2.12 void seq64::seqevent::force_draw() [private], [virtual]

Reimplemented from seq64::gui drawingarea gtk2.

```
12.62.2.13 int seq64::seqevent::idle_redraw( ) [private]
```

Who calls this routine? Probably the default timer routine, but not sure.

Returns

Always returns true.

```
12.62.2.14 void seq64::seqevent::x_to_w ( int x1, int x2, int & x, int & w ) [private]
```

Then it fills in x and the width.

Parameters

	x1	The "left" x value.
	x2	The "right" x value.
out	Х	The destination for the converted x value.
out	W	The destination for the converted width value.

```
12.62.2.15 void seq64::seqevent::drop_event( midipulse tick ) [private]
```

It sets the first byte properly for after-touch, program-change, channel-pressure, and pitch-wheel. The type of event is determined by m_status.

Parameters

tick	The destination time (division, pulse, tick) for the event to be dropped at.
------	--

12.62.2.16 void seq64::seqevent::draw_events_on(Glib::RefPtr< Gdk::Drawable > drawable) [private]

Very similar to seqdata::draw_events_on().

Parameters

drawable	The given drawable object.
	- 0

```
12.62.2.17 void seq64::seqevent::start_paste( ) [private]
```

It gets the clipboard box that selected elements are in, makes a coordinate conversion, and then, sets the m_\leftarrow selected rectangle to hold the (x,y,w,h) of the selected events.

```
12.62.2.18 void seq64::seqevent::change_horz( ) [private]
```

Very similar to seqroll::change_horz(). Basically identical to seqdata::change_horz().

```
12.62.2.19 void seq64::seqevent::convert_x (int x, midipulse & tick ) [inline], [private]
```

Why not just return it normally?

Parameters

		Х	The x (pixel) value to convert.
ĺ	out	tick	The destination for the converted x value.

```
12.62.2.20 void seq64::seqevent::convert_t ( midipulse tick, int & x ) [inline], [private]
```

Why not just return it normally?

Parameters

	tick	The tick (pulse) value to convert.
out	X	The destination for the converted tick value.

```
12.62.2.21 void seq64::seqevent::snap_y(int & y) [inline], [private]
```

Parameters

out	У	The return parameter for the conversion. Why not just return the value?

12.62.2.22 void seq64::seqevent::snap_x(int & x) [private]

- snap = number pulses to snap to
- m_zoom = number of pulses per pixel
- Therefore snap / m_zoom = number of pixels to snap to.

Parameters

out	X	The output destination for the snapped x value.

```
12.62.2.23 void seq64::seqevent::on_realize( ) [private]
```

It calls the base-class version, and then allocates additional resource not allocated in the constructor. Finally, it connects up the change_horz function.

12.62.2.24 bool seq64::seqevent::on_expose_event(GdkEventExpose * ev) [private]

Parameters

ev	The expose event.
----	-------------------

12.62.2.25 bool seq64::seqevent::on_button_press_event (GdkEventButton * ev) [private]

It distinguishes between the Seq24 and Fruity varieties of mouse interaction.

Odd. In the legacy code, each case fell through to the next case to the "default" case! We will assume for now that this is incorrect.

Note that returning "true" from a Gtkmm event-handler stops the propagation of the event to higher-level widgets. The Fruity and Seq24 event handlers return true, always. In the legacy code, though, the fall-through code caused false to be returned, always. Not sure what effect this had. Added some fixes, but then commented them out until better testing can be done.

Parameters

ev T	he button event.
------	------------------

Returns

Returns true if the button-press was handled.

```
12.62.2.26 bool seq64::seqevent::on_button_release_event( GdkEventButton * ev ) [private]
```

It distinguishes between the Seq24 and Fruity varieties of mouse interaction.

Odd. The fruity case fell through to the Seq24 case. We will assume for now that this is correct. Added some fixes, but then commented them out until better testing can be done.

Parameters

```
ev The button event.
```

Returns

Returns true if the button-press was handled.

12.62.2.27 bool seq64::seqevent::on_motion_notify_event(GdkEventMotion * ev) [private]

It distinguishes between the Seq24 and Fruity varieties of mouse interaction.

Odd. The fruity case fell through to the Seq24 case. We will assume for now that this is correct. Added some fixes, but then commented them out until better testing can be done.

Parameters

ev The motion event.

Returns

Returns true if the motion-event was handled.

12.62.2.28 bool seq64::seqevent::on_focus_in_event (GdkEventFocus *) [private]

Parameter "ev" is the focus event, unused.

Returns

Always returns false.

12.62.2.29 bool seq64::seqevent::on_focus_out_event(GdkEventFocus*) [private]

Parameter "ev" is the focus event, unused.

Returns

Always returns false.

12.62.2.30 bool seq64::seqevent::on_key_press_event(GdkEventKey * ev) [private]

It handles deleted a selection via the Backspace or Delete keys, cut via Ctrl-X, copy via Ctrl-C, paste via Ctrl-V, and undo via Ctrl-Z.

Would be nice to provide redo functionality via Ctrl-Y. :-)

Parameters

ev The key-press event.

Returns

Returns true if an event was handled. Only some of the handled events also cause the perform modification flag to be set as a side-effect.

```
12.62.2.31 void seq64::seqevent::on_size_allocate ( Gtk::Allocation & a ) [private]
```

The m window x and m window y values are set to the allocation width and height, respectively.

Parameters

```
a The allocation to be processed.
```

```
12.62.3 Friends And Related Function Documentation
```

```
12.62.3.1 friend struct FruitySeqEventInput [friend]
```

12.62.3.2 friend struct Seq24SeqEventInput [friend]

12.62.4 Field Documentation

12.62.4.1 FruitySeqEventInput seq64::seqevent::m_fruity_interaction [private]

Why should we need both at the same time? Just load the one that is specified in the configuration.

```
12.62.4.2 Seq24SeqEventInput seq64::seqevent::m_seq24_interaction [private]
```

12.62.4.3 sequence& seq64::seqevent::m_seq [private]

12.62.4.4 int seq64::seqevent::m_zoom [private]

12.62.4.5 int seq64::seqevent::m_snap [private]

Same meaning as for the piano roll. This value is the denominator of the note size used for the snap.

```
12.62.4.6 int seq64::seqevent::m_ppqn [private]
```

Used in snap and zoom scaling.

```
12.62.4.7 GdkRectangle seq64::seqevent::m_old [private]
```

12.62.4.8 GdkRectangle seq64::seqevent::m_selected [private]

12.62.4.9 int seq64::seqevent::m_scroll_offset_ticks [private]

12.62.4.10 int seq64::seqevent::m_scroll_offset_x [private]


Set to m_scroll_offset_ticks divided by m_zoom.

```
12.62.4.11 seqdata& seq64::seqevent::m_seqdata_wid [private]
12.62.4.12 bool seq64::seqevent::m_selecting [private]
12.62.4.13 bool seq64::seqevent::m_moving_init [private]
12.62.4.14 bool seq64::seqevent::m_moving [private]
WARNING: This operation seems to have a bug. It makes the events very very long. This bug exists in Seq24.
12.62.4.15 bool seq64::seqevent::m_growing [private]
Does growing work in this view? Need to do some better testing.
12.62.4.16 bool seq64::seqevent::m_painting [private]
12.62.4.17 bool seq64::seqevent::m_paste [private]
12.62.4.18 int seq64::seqevent::m_move_snap_offset_x [private]
12.62.4.19 midibyte seq64::seqevent::m_status [private]
The current status/event byte.
12.62.4.20 midibyte seq64::seqevent::m_cc [private]
The current MIDI CC value.
```

12.63 seq64::seqkeys Class Reference

This class implements the left side piano of the pattern/sequence editor.

Inheritance diagram for seq64::seqkeys:



Public Member Functions

- seqkeys (sequence &seq, perform &p, Gtk::Adjustment &vadjust)
- virtual ∼seqkeys ()

Let's provide a do-nothing virtual destructor.

• void set_scale (int scale)

Principal constructor.

Sets the musical scale, then resets.

void set_key (int key)

Sets the musical key, then resets.

void set_hint_key (int key)

Sets a key to grey so that it can serve as a scale hint.

void set_hint_state (bool state)

Sets the hint state to the given value.

Private Member Functions

virtual void force_draw ()

Forces a draw operation on the whole window.

void set_listen_button_press (GdkEventButton *ev)

Sneaky accessors for the segroll friend.

- void set_listen_button_release (GdkEventButton *ev)
- void set listen motion notify (GdkEventMotion *ev)
- · void draw_area ()

Draws the updated pixmap on the drawable area of the window where the keys' location is hardwired.

void update_pixmap ()

Updates the pixmaps to prepare it for the next draw operation.

void convert_y (int y, int ¬e)

Takes the screen y coordinate, and returns the note value in the second parameter.

void draw key (int key, bool state)

Draws the given key according to the given state.

· void change_vert ()

Changes the y offset of the scrolling, and the forces a draw.

- void update sizes ()
- · void reset ()

Resetting the keys view updates the pixmap and queues up a draw operation.

bool is_black_key (int key) const

Detects a black key.

• void on_realize ()

Implements the on-realize event.

bool on_expose_event (GdkEventExpose *ev)

Implements the on-expose event, by drawing on the window.

bool on_button_press_event (GdkEventButton *ev)

Implements the on-button-press event callback.

bool on_button_release_event (GdkEventButton *ev)

Implements the on-button-release event callback.

bool on_motion_notify_event (GdkEventMotion *p0)

Implements the on-motion-notify event handler.

bool on_enter_notify_event (GdkEventCrossing *p0)

Implements the on-enter notification event handler.

• bool on_leave_notify_event (GdkEventCrossing *p0)

Implements the on-leave notification event handler.

bool on_scroll_event (GdkEventScroll *ev)

Implements the on-scroll-event notification event handler.

void on_size_allocate (Gtk::Allocation &)

Implements the on-size-allocation notification event handler.

Private Attributes

• sequence & m_seq

The sequence object that the keys pane will be using.

int m_scroll_offset_key

Provides the value of the current top key in the keys pane.

int m_scroll_offset_y

Provides the value of the current top key in the keys pane in units of relative pixels.

bool m_hint_state

Indicates if a piano key is set to indicate where on the pitch scale the mouse cursor is sitting.

int m_hint_key

Indicates the current y-value of the mouse pointer in units of key value.

bool m_keying

Set to true while the left mouse button is being pressed.

• int m_keying_note

The note to be played when selected in the seqkeys pane.

• int m scale

This member holds the scale value for the musical scale for the current edit of the sequence.

int m key

This member holds the key value for the musical key for the current edit of the sequence.

· bool m_show_octave_letters

The default value is to show the octave letters on the vertical virtual keyboard.

Friends

- · class segroll
- · class FruitySeqRollInput

Additional Inherited Members

12.63.1 Detailed Description

Note the friends of this class, seqroll and FruitySeqRollInput. Where is Seq24SeqRollInput? Gone. It has been folded back into seqroll.

12.63.2 Constructor & Destructor Documentation

12.63.2.1 seq64::seqkeys::seqkeys (sequence & seq, perform & p, Gtk::Adjustment & vadjust)

Parameters

seq	Provides the sequence object to which this seqkeys pane is associated.
р	Provides the performance object to which this seqkeys pane (and all sequences) are associated.
vadjus	The range object for the vertical scrollbar linked to the position in the seqkeys pane.

12.63.2.2 virtual seq64::seqkeys::~seqkeys() [inline], [virtual]

12.63.3 Member Function Documentation

12.63.3.1 void seq64::seqkeys::set_scale (int scale)

This function is called by the seqedit class.

Parameters

12.63.3.2 void seq64::seqkeys::set_key (int key)

Parameters

key The musical key v	value to be set.
-----------------------	------------------

12.63.3.3 void seq64::seqkeys::set_hint_key (int key)

If m_hint_state is true, the key is drawn (again).

Parameters

et the hint-key to.	The key value	key
---------------------	---------------	-----

12.63.3.4 void seq64::seqkeys::set_hint_state (bool state)

Parameters

state	Provides the value for hinting, where true == on, false == off.
-------	---

```
12.63.3.5 void seq64::seqkeys::force_draw( ) [private], [virtual]
```

Unlike most other overridden versions of force_draw(), this one does not call the base-class version.

Reimplemented from seq64::gui_drawingarea_gtk2.

12.63.3.6 void seq64::seqkeys::set_listen_button_press (GdkEventButton * ev) [inline], [private]

From the stazed code.

Parameters

ev The event to be forwarded from the seqroll.

```
12.63.3.7 void seq64::seqkeys::set_listen_button_release ( GdkEventButton * ev ) [inline], [private]
12.63.3.8 void seq64::seqkeys::set_listen_motion_notify ( GdkEventMotion * ev ) [inline], [private]
12.63.3.9 void seq64::seqkeys::draw_area ( ) [private]
12.63.3.10 void seq64::seqkeys::update_pixmap ( ) [private]
```

This function draws the keys, which range from 0 to 127 (SEQ64_MIDI_COUNT_MAX - 1 = c_num_keys - 1). Every octave, a key letter and number (e.g. "C4") is shown. The letter is adjusted to match the current scale (e.g. "C#4").

We want to support an option to show the key number rather than the note letter/number combination, and perhaps to toggle between them. The current difficulty is that the fonts used are just a little to high to fit within the vertical limits of each key. We really don't want to change the vertical size at this time, so we just print every other note value.

Also note that this algorithm draws from the top down, so we have to account for that.

```
12.63.3.11 void seq64::seqkeys::convert_y ( int y, int & note ) [private]
```

Parameters

	У	The y (vertical) screen coordinate to convert.
out	note	The destination for the note calculation. This would be better as a return value.

```
12.63.3.12 void seq64::seqkeys::draw_key( int key, bool state) [private]
```

It accounts for the black keys and the white keys, and for the highlighting of the active key.

Parameters

key	The key to be drawn.
state	How the key is to be drawn, where false == normal, true == grayed. A key is greyed when the mouse
	cursor is at the same vertical location on the piano as the key.

```
12.63.3.13 void seq64::seqkeys::change_vert( ) [private]
```

Weird, in seq24 and here, the following was used, completely by accident! We fixed it, but must beware!

```
m_scroll_offset_y = m_scroll_offset_key * c_key_y, // comma operator!!!
force_draw();

12.63.3.14 void seq64::seqkeys::update_sizes( ) [private]

12.63.3.15 void seq64::seqkeys::reset( ) [private]

12.63.3.16 bool seq64::seqkeys::is_black_key(int key) const [inline], [private]
```

Parameters

key	The key to analyze.
-----	---------------------

Returns

Returns true if the key is black (value 1, 3, 6, 8, or 10).

```
12.63.3.17 void seq64::seqkeys::on_realize( ) [private]
```

Call the base-class version and then allocates resources that could not be allocated in the constructor. It connects the change vert() function and then calls it.

12.63.3.18 bool seq64::seqkeys::on_expose_event(GdkEventExpose * ev) [private]

Parameters

ev The	expose-event object.
--------	----------------------

12.63.3.19 bool seq64::seqkeys::on_button_press_event (GdkEventButton * ev) [private]

It handles the left and right buttons. The left button, pressed on the piano keyboard, causes m_keying to be set to true, and the given note to play. The right button toggles the note display between letter/number and MIDI note number.

Parameters

	ev	The mouse-button event to use.
--	----	--------------------------------

Returns

Always returns true.

12.63.3.20 bool seq64::seqkeys::on_button_release_event(GdkEventButton * ev) [private]

It currently handles only the left button, and only if m_keying is true.

This function is used after pressing on one of the keys on the left-side piano keyboard, to make it play, and turns off the playing of the note.

Parameters

ev The button-event.

Returns

Always returns true.

12.63.3.21 bool seq64::seqkeys::on_motion_notify_event(GdkEventMotion * p0) [private]

This allows rolling down the keyboard, playing the notes one-by-one.

Parameters

```
p0 The motion event.
```

Returns

Always returns false.

12.63.3.22 bool seq64::seqkeys::on_enter_notify_event(GdkEventCrossing * p0) [private]

This greys the current key.

12.63.3.23 bool seq64::seqkeys::on_leave_notify_event(GdkEventCrossing * p0) [private]

This un-greys the current key and stops playing the note.

12.63.3.24 bool seq64::seqkeys::on_scroll_event(GdkEventScroll * ev) [private]

Note that there is no usage of the modifier keys (e.g. Shift or Ctrl). Compare this function to seqedit::on_scroll_← event().

Parameters

ev Provides the direction of the scroll event.

Returns

Always returns true.

12.63.3.25 void seq64::seqkeys::on_size_allocate (Gtk::Allocation & all) [private]

Parameters

all Provies the allocation and its width and height.


```
12.63.4 Friends And Related Function Documentation
12.63.4.1 friend class segroll [friend]
12.63.4.2 friend class FruitySeqRollInput [friend]
12.63.5 Field Documentation
12.63.5.1 sequence& seq64::seqkeys::m_seq [private]
12.63.5.2 int seq64::seqkeys::m_scroll_offset_key [private]
Modified in change_vert().
12.63.5.3 int seq64::seqkeys::m_scroll_offset_y [private]
Modified in change_vert().
12.63.5.4 bool seq64::seqkeys::m_hint_state [private]
12.63.5.5 int seq64::seqkeys::m_hint_key [private]
12.63.5.6 bool seq64::seqkeys::m_keying [private]
Used in playing the sound for each note as it is clicked in the seqkeys pane.
12.63.5.7 int seq64::seqkeys::m_keying_note [private]
12.63.5.8 int seq64::seqkeys::m_scale [private]
12.63.5.9 int seq64::seqkeys::m_key [private]
12.63.5.10 bool seq64::seqkeys::m_show_octave_letters [private]
```

If false, then the MIDI key numbers are shown instead. This is a new feature of Sequencer64.

12.64 seq64::seqmenu Class Reference

This class handles the right-click menu of the sequence slots in the pattern window.

Inheritance diagram for seq64::seqmenu:



Public Member Functions

seqmenu (perform &a_p)

Principal constructor.

virtual ∼seqmenu ()

Provides a rote base-class destructor.

• int current_seq () const

'Getter' function for member m_current_seq We're changing the name, so that "seq" indicates an integer by (an imperfect) convention.

· bool is modified () const

'Getter' function for member m_modified

Protected Member Functions

void current seq (int seq)

'Setter' function for member m_current_seq

• void set_edit_sequence (int seqnum)

'Setter' function for member m_edit_sequence Pass in -1 to disable the edit-sequence number.

void unset_edit_sequence (int seqnum)

'Setter' function for member m_edit_sequence Disable the edit-sequence number if it matches the parameter.

bool is edit sequence (int seqnum) const

'Getter' function for member m_edit_sequence Tests the parameter against m_edit_sequence.

· void is modified (bool flag)

'Setter' function for member m_modified

• sequence * get_current_sequence () const

'Getter' function for member m_mainperf.get_sequence(current_seq()) This call is used many, many times, and well worth wrapping.

sequence * get_sequence (int seqnum) const

Forwards the get-sequence call to the perform object.

bool is_current_seq_active () const

Forwards the is-sequence-active check to the perform object.

bool is_current_seq_in_edit () const

Forwards the is-sequence-in-edit check to the perform object.

• void new current sequence ()

Forwards the new-current-sequence call to the perform object.

void new_sequence (int seqnum)

Forwards the new-sequence call to the perform object.

• void delete_current_sequence ()

Forwards the delete-sequence call to the perform object.

void toggle_current_sequence ()

Forwards the sequence-playing-toggle call to the perform object.

void popup_menu ()

This function sets up the pattern menu entries.

void seq_edit ()

This menu callback launches the sequence-editor (pattern editor) window.

void seq_event_edit ()

This menu callback launches the new event editor window.

virtual void seq_set_and_edit (int seqnum)

Sets the current sequence and then acts as if the user had clicked on its slot.

virtual void seq_set_and_eventedit (int seqnum)

Sets the current sequence and then acts as if the user had right-clicked on its slot and selected "Event Edit".

Private Member Functions

• void seq new ()

This function sets the new sequence into the perform object, a bit prematurely, though.

void seq_copy ()

Copies the selected (current) sequence to the clipboard sequence.

void seq_cut ()

Deletes the selected (current) sequence and copies it to the clipboard sequence, if it is not in edit mode.

void seq_paste ()

Pastes the sequence clipboard into the current sequence, if the current sequence slot is not active.

void seq_clear_perf ()

If the current sequence is active, this function pushes a trigger undo in the main perform object, clears its sequence triggers for the current sequence, and sets the dirty flag of the sequence.

• void set bus and midi channel (int a bus, int a ch)

Sets up the bus, MIDI channel, and dirtiness flag of the current sequence in the main perform object, as per the give parameters.

· void set transposable (bool flag)

Sets the "is-transposable" flag of the current sequence.

void mute_all_tracks ()

Mutes all tracks in the main perform object.

void unmute_all_tracks ()

Unmutes all tracks in the main perform object.

void toggle all tracks ()

Toggles the mute-status of all tracks in the main perform object.

- virtual void redraw (int a_sequence)=0
- void on_realize ()

Private Attributes

• Gtk::Menu * m menu

The menu to pop up when the right-click action is used either on a mainwid pattern slot or on a perfedit pattern name.

• perform & m_mainperf

Provides a reference to the central (non-UI) object involved in managing a song and performance.

· sequence m clipboard

Holds a copy of data concerning a sequence, which can then be pasted into another pattern slot.

seqedit * m_seqedit

Points to the latest sequdit object, if created.

• eventedit * m_eventedit

Points to the latest eventedit object, if created.

int m_current_seq

References the current sequence by sequence number.

bool m_modified

Indicates if a sequence has been created.

12.64.1 Detailed Description

It is an abstract base class.

12.64.2 Constructor & Destructor Documentation

12.64.2.1 seq64::seqmenu::seqmenu (perform & p)

Apart from filling in some of the members, this function initializes the clipboard, so that we don't get a crash on a paste with no previous copy.

Parameters

p The main performance object representing the whole MIDI song.

```
12.64.2.2 seq64::segmenu::~segmenu() [virtual]
```

A rote destructor.

This is necessary in an abstraction base class.

If we determine that we need to delete the m_seqedit pointer, we can do it here. But that is not likely, because we can have many new seqedit objects in play, because we can edit many at once.

```
12.64.3 Member Function Documentation
```

```
12.64.3.1 int seq64::seqmenu::current_seq() const [inline]
12.64.3.2 bool seq64::seqmenu::is_modified() const [inline]
12.64.3.3 void seq64::seqmenu::current_seq(int seq) [inline], [protected]
12.64.3.4 void seq64::seqmenu::set_edit_sequence(int seqnum) [inline], [protected]
Now a pass-along to the perform object.
```

```
12.64.3.5 void seq64::seqmenu::unset_edit_sequence( int seqnum ) [inline], [protected]
12.64.3.6 bool seq64::seqmenu::is_edit_sequence( int seqnum ) const [inline], [protected]
```

Returns true if that member is not -1, and the parameter matches it. Now a pass-along to the perform object.

```
12.64.3.7 void seq64::seqmenu::is_modified ( bool flag ) [inline], [protected]

12.64.3.8 sequence* seq64::seqmenu::get_current_sequence() const [inline], [protected]

12.64.3.9 sequence* seq64::seqmenu::get_sequence(int seqnum) const [inline], [protected]

12.64.3.10 bool seq64::seqmenu::is_current_seq_active() const [inline], [protected]

12.64.3.11 bool seq64::seqmenu::is_current_seq_in_edit() const [inline], [protected]

12.64.3.12 void seq64::seqmenu::new_current_sequence() [inline], [protected]

12.64.3.13 void seq64::seqmenu::delete_current_sequence() [inline], [protected]

12.64.3.14 void seq64::seqmenu::delete_current_sequence() [inline], [protected]

12.64.3.15 void seq64::seqmenu::toggle_current_sequence() [inline], [protected]

12.64.3.16 void seq64::seqmenu::popup_menu() [protected]
```

It also sets up the pattern popup menu entries that are used in mainwid. Note that, for the selected sequence, the "Edit" and "Event Edit" menu entries are not included if a pattern editor or event editor is already running. The new event editor seems to create far-reaching problems that we do not yet understand, so it is now possible to disable it at build time. We have mitigated most of those problems by not allowing both a seq_edit() and a seq_event_edit() at the same time.

12.64.3.17 void seq64::seqmenu::seq_edit() [protected]

If it is already open for that sequence, this function just raises it.

Note that the m segedit member to which we save the new pointer is currently there just to avoid a compiler warning.

Also, if a new sequences is created, we set the m_modified flag to true, even though the sequence might later be deleted. Too much modification to keep track of!

An oddity is that calling show all() here does not work unless the seqedit() constructor makes its show all() call.

```
12.64.3.18 void seq64::seqmenu::seq_event_edit() [protected]
```

If it is already open for that sequence, this function just raises it.

Note that the m_eventedit member to which we save the new pointer is currently there just to avoid a compiler warning.

This menu entry is available only if the selected sequence is active. That is, if the sequence has already been created.

An oddity is that we need the show_all() call here in order to see the dialog. A situation different from that for sequdit! However, now it doesn't seem to be needed, and we have put it back into the eventedit constructor.

```
12.64.3.19 void seq64::seqmenu::seq_set_and_edit(int seqnum) [protected], [virtual]
```

How do we account for the current screenset? It might not matter if the mute/unmute keystrokes were designed to work only with the current screenset.

Parameters

Reimplemented in seq64::mainwid.

```
12.64.3.20 void seq64::seqmenu::seq_set_and_eventedit(int seqnum) [protected], [virtual]
```

Parameters

seqnum	The number of the sequence to event-edit.

Reimplemented in seq64::mainwid.

```
12.64.3.21 void seq64::seqmenu::seq_new( ) [private]
```

For one thing, if current_seq() is either a -1 or is greater than the maximum allowed sequence number, perform ::is_active() will return false, and we have no idea whether the sequence is not active or the sequence number is just invalid. So we need to check the pointer we got before trying to use it.

```
12.64.3.22 void seq64::seqmenu::seq_copy() [private]
```

We use a more appropriate function than operator =() here: sequence::partial_assign().

Todo Can be offloaded to a perform member function that accepts a sequence clipboard non-const reference parameter.

```
12.64.3.23 void seq64::seqmenu::seq_cut( ) [private]
```

Todo A lot of seq_cut() can be offloaded to a (new) perform member function that takes a sequence clipboard non-const reference parameter.

```
12.64.3.24 void seq64::seqmenu::seq_paste( ) [private]
```

Then it sets the dirty flag for the destination sequence.

Todo All of seq_paste() can be offloaded to a (new) perform member function with a const clipboard reference parameter.

```
12.64.3.25 void seq64::seqmenu::seq_clear_perf( ) [private]
```

Todo All of seq_paste() can be offloaded to a (new) perform member function.

```
12.64.3.26 void seq64::seqmenu::set_bus_and_midi_channel( int bus, int ch ) [private]
```

Parameters

bus	The MIDI buss number to set (bus vs buss? You decide.)
ch	The MIDI channel number to set.

12.64.3.27 void seg64::segmenu::set_transposable(bool flag) [private]

Parameters

```
12.64.3.28 void seq64::seqmenu::mute_all_tracks( ) [private]
```

12.64.3.29 void seq64::seqmenu::unmute_all_tracks() [private]

```
12.64.3.30 void seq64::seqmenu::toggle_all_tracks( ) [private]
12.64.3.31 virtual void seq64::seqmenu::redraw (int a_sequence) [private], [pure virtual]
Implemented in seq64::mainwid, and seq64::perfnames.
12.64.3.32 void seq64::segmenu::on_realize() [private]
12.64.4 Field Documentation
12.64.4.1 Gtk::Menu* seq64::seqmenu::m_menu [private]
12.64.4.2 perform& seq64::seqmenu::m_mainperf [private]
12.64.4.3 sequence seq64::seqmenu::m_clipboard [private]
12.64.4.4 seqedit* seq64::seqmenu::m_seqedit [private]
Change Note Added by Chris on 2015-08-02 based on compiler warnings and a comment warning in the seq_edit()
function. We'll save the result of that function here, and will let valgrind tell us later if Gtkmm takes care of it.
```

```
12.64.4.5 eventedit* seq64::seqmenu::m_eventedit [private]
12.64.4.6 int seq64::seqmenu::m_current_seq [private]
12.64.4.7 bool seq64::seqmenu::m_modified [private]
```

Todo We need to make sure that the perform object is in control of the modification flag.

12.65 seq64::seqroll Class Reference

Implements the piano roll section of the pattern editor.

Inheritance diagram for seq64::seqroll:



Public Member Functions

• seqroll (perform &perf, sequence &seq, int zoom, int snap, seqkeys &seqkeys_wid, int pos, Gtk::Adjustment &hadjust, Gtk::Adjustment &vadjust, int ppqn=SEQ64_USE_DEFAULT_PPQN)

Principal constructor.

virtual ∼seqroll ()

Provides a destructor to delete allocated objects.

void set_snap (int snap)

Sets the snap to the given value, and then resets the view.

void set_zoom (int zoom)

Sets the zoom to the given value, and then resets the view.

· void set note length (int note length)

'Setter' function for member m_note_length

• int note_off_length () const

'Getter' function for member m_note_length, adjusted for the note_off_margin.

bool add_note (midipulse tick, int note, bool paint=true)

Convenience wrapper for sequence::add_note().

void set_key (int key)

Sets the music key to the given value, and then resets the view.

• void set_scale (int scale)

Sets the music scale to the given value, and then resets the view.

void set_data_type (midibyte status, midibyte control)

Sets the status to the given parameter, and the CC value to the given optional control parameter, which defaults to 0.

void set background sequence (bool state, int seq)

This function sets the given sequence onto the piano roll of the pattern editor, so that the musician can have another pattern to play against.

• void update_pixmap ()

This function draws the background pixmap on the main pixmap, and then draws the events on it.

• void update sizes ()

Update the sizes of items based on zoom, PPQN, BPM, BW (beat width) and more.

void update_background ()

Updates the background of this window.

• void draw_background_on_pixmap ()

Draws the main pixmap.

• void draw_events_on_pixmap ()

Fills the main pixmap with events.

void draw_selection_on_window ()

Draws the current selecton on the main window.

void draw_progress_on_window ()

Draw a progress line on the window.

void reset ()

This function basically resets the whole widget as if it were realized again.

void update_and_draw (int force=false)

Wraps up some common code.

• void redraw ()

Redraws unless m_ignore_redraw is true.

void redraw_events ()

Redraws events unless m_ignore_redraw is true.

· void start_paste ()

Starts a paste operation.

- void complete paste ()
- void complete_paste (int x, int y)

Completes a paste operation.

void follow_progress ()

Private Member Functions

virtual void force_draw ()

Set the pixmap into the window and then draws the selection on it.

void horizontal adjust (double step)

This function provides optimization for the on_scroll_event() function.

void vertical_adjust (double step)

This function provides optimization for the on_scroll_event() function.

void snap_y (int &y)

Snaps the y value to the piano-key "height".

void snap_x (int &x)

Performs a 'snap' operation on the x coordinate.

- void convert_xy (int x, int y, midipulse &ticks, int ¬e)
- void convert tn (midipulse ticks, int note, int &x, int &y)

This function takes the given note and tick, and returns the screen coordinates via the pointer parameters.

void xy_to_rect (int x1, int y1, int x2, int y2, int &x, int &y, int &w, int &h)

Converts rectangle corner coordinates to a starting coordinate, plus a width and height.

void convert_tn_box_to_rect (midipulse tick_s, midipulse tick_f, int note_h, int note_l, int &x, int &y, int &w, int &h)

Converts a tick/note box to an x/y rectangle.

• void convert_sel_box_to_rect (midipulse tick_s, midipulse tick_f, int note_h, int note_l)

A convenience function wrapping a common call to convert_tn_box_to_rect().

void get selected box (midipulse &tick s, int ¬e h, midipulse &tick f, int ¬e l)

A convenience function wrapping a common call to m_seq.get_selected_box() and convert_tn_box_to_rect().

void draw_events_on (Glib::RefPtr< Gdk::Drawable > draw)

Draws events on the given drawable area.

• int idle redraw ()

Draw the events on the main window and on the pixmap.

- int idle_progress ()
- void change_horz ()

Change the horizontal scrolling offset and redraw.

· void change_vert ()

Change the vertical scrolling offset and redraw.

void move_selection_box (int dx, int dy)

Function to allow motion of the selection box via the arrow keys.

void move_selected_notes (int dx, int dy)

Proposed new function to encapsulate the movement of selections even more fully.

void grow_selected_notes (int dx)

Proposed new function to encapsulate the movement of selections even more fully.

void set_adding (bool adding)

Changes the mouse cursor pixmap according to whether a note is being added or not.

void update_mouse_pointer (bool adding=false)

Updates the mouse pointer, implementing a context-sensitive mouse.

- bool button_press_initial (GdkEventButton *ev, int &norm_x, int &snapped_x, int &snapped_y)
- void align selection (midipulse &tick s, int ¬e h, midipulse &tick f, int ¬e l, int snapped x)

Get the box that selected elements are in.

• bool button_press (GdkEventButton *ev)

Implements the on-button-press event handling for the Seq24 style of mouse interaction.

bool button_release (GdkEventButton *ev)

Implements the on-button-release event handling for the Seq24 style of mouse interaction.

• bool motion_notify (GdkEventMotion *ev)

Seq24-style on-motion mouse interaction.

void clear_selected ()

'Setter' function for member m_old

· void clear old ()

'Setter' function for member m_old

· void clear flags ()

Clears all the mouse-action flags.

int scroll offset x (int x) const

Useful x calculation.

int scroll_offset_y (int y) const

Useful y calculation.

void set_current_offset_x_y (int x, int y)

Useful x calculation.

• bool adding () const

'Getter' function for member m_adding

• bool selecting () const

'Getter' function for member m_selecting

· bool growing () const

'Getter' function for member m_growing

· bool normal action () const

Indicates if we're drag-pasting, selecting, moving, growing, or pasting.

bool select_action () const

Indicates if we're selecting, moving, growing, or pasting.

bool drop_action () const

Indicates if we're moving or pasting.

• bool moving () const

'Getter' function for member m_moving

void on_realize ()

Implements the on-realize event handling.

bool on expose event (GdkEventExpose *ev)

Implements the on-expose event handling.

bool on_button_press_event (GdkEventButton *ev)

Implements the on-button-press event handling.

bool on_button_release_event (GdkEventButton *ev)

Implements the on-button-release event handling.

• bool on_motion_notify_event (GdkEventMotion *ev)

Implements the on-motion-notify event handling.

bool on_focus_in_event (GdkEventFocus *)

Implements the on-focus event handling.

bool on_focus_out_event (GdkEventFocus *)

Implements the on-unfocus event handling.

• bool on_key_press_event (GdkEventKey *ev)

Implements the on-key-press event handling.

bool on_scroll_event (GdkEventScroll *a_ev)

Implements the on-scroll event handling.

• void on_size_allocate (Gtk::Allocation &)

Implements the on-size-allocate event handling.

bool on_leave_notify_event (GdkEventCrossing *p0)

Implements the on-leave-notify event handling.

bool on_enter_notify_event (GdkEventCrossing *p0)

Implements the on-enter-notify event handling.

Private Attributes

Gtk::Adjustment & m_horizontal_adjust

We need direct access to the horizontal scrollbar if we want to be able to make it follow the progress bar.

Gtk::Adjustment & m_vertical_adjust

We need direct access to the vertical scrollbar if we want to be able to make it follow PageUp and PageDown.

· rect m old

The previous selection rectangle, used for undrawing it.

· rect m selected

Used in moving and pasting notes.

• sequence & m_seq

Provides a reference to the sequence represented by piano roll.

seqkeys & m_seqkeys_wid

Holds a reference to the seqkeys pane that is associated with the seqroll piano roll.

FruitySeqRollInput m_fruity_interaction

Provides a fruity input object, whether it is needed or not.

int m_pos

A position value.

• int m zoom

Zoom setting, means that one pixel == m_zoom ticks.

int m_snap

The grid-snap setting for the piano roll grid.

• int m ppqn

The value of PPQN for the current MIDI song.

• int m_note_length

Holds the note length in force for this sequence.

int m_scale

Indicates the musical scale in force for this sequence.

int m_key

Indicates the musical key in force for this sequence.

· bool m adding

Set when in note-adding mode.

• bool m_selecting

Set when highlighting a bunch of events.

bool m moving

Set when moving a bunch of events.

• bool m_moving_init

Indicates the beginning of moving some events.

bool m_growing

Indicates that the notes are to be extended or reduced in length.

bool m_painting

Indicates the painting of events.

bool m_paste

Indicates that we are in the process of painting notes.

· bool m is drag pasting

Indicates the drag-pasting of events.

bool m_is_drag_pasting_start

Indicates the drag-pasting of events.

· bool m justselected one

Indicates the selection of one event.

int m_move_delta_x

Tells where the dragging started, the x value.

int m_move_delta_y

Tells where the dragging started, the y value.

• int m_move_snap_offset_x

This item is used in the fruityseqroll module.

• int m_progress_x

Provides the location of the progress bar.

· int m scroll offset ticks

The horizontal value of the scroll window in units of ticks/pulses/divisions.

int m_scroll_offset_key

The vertical offset of the scroll window in units of MIDI notes/keys.

• int m scroll offset x

The horizontal value of the scroll window in units of pixels.

· int m scroll offset y

The vertical value of the scroll window in units of pixels.

· int m background sequence

Holds the value of the musical background sequence that is shown in cyan (formerly grey) on the background of the piano roll.

· bool m drawing background seq

Set to true if the drawing of the background sequence is to be done.

· midibyte m_status

Set to true to avoid the call to update_and_draw().

midibyte m_cc

The current MIDI control value selected in the sequdit.

Friends

class FruitySeqRollInput

This friend implements fruity interaction-specific behavior.

· class seqedit

For accessing on_key_press_event().

Additional Inherited Members

12.65.1 Constructor & Destructor Documentation

12.65.1.1 seq64::seqroll::seqroll (perform & p, sequence & seq, int zoom, int snap, seqkeys & seqkeys_wid, int pos, Gtk::Adjustment & hadjust, Gtk::Adjustment & vadjust, int ppqn = SEQ64_USE_DEFAULT_PPQN)

Parameters

p	The performance object that helps control this piano roll. Note that we can get the perform object from the sequence, and save a parameter. Low priority change.
seq	The sequence object represented by this piano roll.
zoom	The initial zoom of this piano roll.
snap	The initial grid snap of this piano roll.
seqkeys_wid	A reference to the piano keys window that is shown to the left of this piano roll.
pos	A position parameter. See the description of seqroll::m_pos. This is actually the sequence number, and is currently unused. However, we're sure we can find a use for it sometime.

Parameters

hadjust	Represents the horizontal scrollbar of this window. It is actually created by the "parent" sequential object.
vadjust	Represents the vertical scrollbar of this window. It is actually created by the "parent" sequential object.
ppqn	The initial value of the PPQN for this sequence. Useful in scale calculations.

```
12.65.1.2 seq64::seqroll::~seqroll() [virtual]
```

The only thing to delete here is the clipboard. Except it is never used, so is commented out.

12.65.2 Member Function Documentation

```
12.65.2.1 void seq64::seqroll::set_snap ( int snap ) [inline]
```

Parameters

Provides the sname value to set.

12.65.2.2 void seq64::seqroll::set_zoom (int zoom)

Parameters

```
12.65.2.3 void seq64::seqroll::set_note_length ( int note_length ) [inline]
```

12.65.2.4 int seq64::seqroll::note_off_length() const [inline]

12.65.2.5 bool seq64::seqroll::add_note (midipulse tick, int note, bool paint = true)

The length parameters is obtained from the note_off_length() function. This sets the note length at a little less than the snap value.

Parameters

tick	The time destination of the new note, in pulses.
note	The pitch destination of the new note.
paint	If true, repaint to be left with just the inserted event. The default is true. The value of false is useful in inserting a number of events and saving the repainting until last. It is a bit tricky, as the default paint value for sequence::add_note() is false.

12.65.2.6 void seq64::seqroll::set_key (int key)

Parameters

key	The desired key value.
-----	------------------------

12.65.2.7 void seq64::seqroll::set_scale (int scale)

Parameters

scale	The desired scale value.
scaie	i ne desired scale value.

12.65.2.8 void seq64::seqroll::set_data_type(midibyte status, midibyte control) [inline]

Unlike the same function in seqevent, this version does not redraw. Used by seqedit.

12.65.2.9 void seq64::seqroll::set_background_sequence (bool state, int seq)

The state parameter sets the boolean m_drawing_background_seq.

Parameters

state	If true, the background sequence will be drawn.
seq	Provides the sequence number, which is checked against the SEQ64_IS_LEGAL_SEQUENCE() macro before being used. This macro allows the value SEQ64_SEQUENCE_LIMIT, which disables the background sequence.

```
12.65.2.10 void seq64::seqroll::update_pixmap( )
12.65.2.11 void seq64::seqroll::update_sizes( )
```

It brings the scrollbar back to the beginning, resets the upper limit to the number of ticks in the sequence, sets the page-size based on the window size and the zoom factor.

The horizontal step increment is 1 semiquaver (1/16) note per zoom level. The horizontal page increment is currently always one bar. We may want to make that larger for scrolling after the progress bar.

Tha maximum value set for the scrollbar brings it to the last "page" of the piano roll.

The vertical size are also adjusted. More on the story later.

```
12.65.2.12 void seq64::seqroll::update_background()
```

The first thing done is to clear the background, painting it white.

```
12.65.2.13 void seq64::seqroll::draw_background_on_pixmap ( )
```

12.65.2.14 void seg64::segroll::draw_events_on_pixmap()

Just calls draw_events_on().

```
12.65.2.15 void seq64::seqroll::draw_selection_on_window( )
```

Note the parameters of draw_drawable(), which we need to be sure of to draw thicker boxes.

```
    x and y position of rectangle to draw
    x and y position in drawable where rectangle should be drawn
    width and height of rectangle to draw
```

A final parameter of false draws an unfilled rectangle. Orange makes it a little more clear that we're pasting, I think. We also want to try to thicken the lines somehow.

```
12.65.2.16 void seq64::seqroll::draw_progress_on_window()
```

This is done by first blanking out the line with the background, which contains white space and grey lines, using the the draw_drawable function. Remember that we wrap the draw_drawable() function so it's parameters are xsrc, ysrc, xdest, ydest, width, and height.

Note that the progress-bar position is based on the sequence::get_last_tick() value, the current zoom, and the current scroll-offset x value.

Finally, we had an issue with the selection box flickering, which seems to be solved satisfactorily by not drawing it if a select action is in force. Hopefully no one needs to select notes on the fly and see the progress bar moving at the same time! Another tactic is to draw progress only when the performance is running. This has the benefit/drawback that the progress bar is left where it stops. Consider an enumeration of options: normal, when-not-selecting, and when-running.

```
12.65.2.17 void seq64::seqroll::reset ( )
```

It's almost identical to the change_horz() function, just calling update_sizes() before update_and_draw().

```
12.65.2.18 void seq64::seqroll::update_and_draw ( int force = false )
```

Parameters

force If true, force an immediate draw, otherwise just queue up a draw.

```
12.65.2.19 void seq64::seqroll::redraw ( )
```

Somewhat similar to seqevent::redraw(). Actually, we don't seem to need to ignore redraw when making settings in the seqedit constructor, so this member no longer exists.

```
12.65.2.20 void seq64::seqroll::redraw_events ( )
```

Actually, that member is not needed and no longer exists.

```
12.65.2.21 void seq64::seqroll::complete_paste()
12.65.2.22 void seq64::seqroll::complete_paste(int x, int y)
12.65.2.24 void seq64::seqroll::follow_progress() [inline]
12.65.2.25 void seq64::seqroll::force_draw() [private], [virtual]
Reimplemented from seq64::gui_drawingarea_gtk2.
12.65.2.26 void seq64::seqroll::horizontal_adjust(double step) [inline], [private]
```

A duplicate of the one in seqedit.

Parameters

 step
 Provides the step value to use for adjusting the horizontal scrollbar. See

 gui_drawingarea_gtk2::scroll_hadjust() for more information.

```
12.65.2.27 void seq64::seqroll::vertical_adjust(double step) [inline], [private]
```

A duplicate of the one in seqedit.

Parameters

step Provides the step value to use for adjusting the vertical scrollbar. See gui_drawingarea_gtk2::scroll_vadjust() for more information.

```
12.65.2.28 void seq64::seqroll::snap_y ( int & y ) [inline], [private]
```

Parameters

```
out y The y-value to be snapped.
```

```
12.65.2.29 void seq64::seqroll::snap_x ( int & x ) [private]
```

This function is similar to snap_y(), but it calculates a modulo value from the snap and zoom settings.

```
- m_snap = number pulses to snap to
- m_zoom = number of pulses per pixel
```

Therefore, m_snap / m_zoom = number pixels to snap to.

Parameters

out	Х	Provides the x-value to be snapped and returned. A return value would be better.]
-----	---	--	---

12.65.2.30 void seq64::seqroll::convert_xy (int x, int y, midipulse & ticks, int & note) [private]

12.65.2.31 void seq64::seqroll::convert_tn (midipulse tick, int note, int & x, int & y) [private]

This function is the "inverse" of convert_xy().

Parameters

	tick	Provides the horizontal value in MIDI pulses.
	note	Provides the vertical value, a note value.
out	X	Provides the destination x value of the coordinate.
out	У	Provides the destination y value of the coordinate.

12.65.2.32 void seq64::seqroll::xy_to_rect(int x1, int y1, int x2, int y2, int & x, int & y, int & w, int & h) [private]

This function checks the mins / maxes, and then fills in the x, y, width, and height values.

We should refactor this function to use the utility class seqroll::rect as the destination for the conversion.

Parameters

	x1	The x value of the first corner.	
	y1	y1 The y value of the first corner.	
	x2	The x value of the second corner.	
	y2	The y value of the second corner.	
out	Х	The destination for the x value in pixels.	
out	У	The destination for the y value in pixels.	
out	W	The destination for the rectangle width in pixels.	
out	h	The destination for the rectangle height value in pixels.	

12.65.2.33 void seq64::seqroll::convert_tn_box_to_rect (midipulse *tick_s*, midipulse *tick_f*, int *note_h*, int *note_l*, int & x, int & y, int & w, int & h) [private]

We should refactor this function to use the utility class seqroll::rect as the destination for the conversion.

Parameters

	tick_s	The starting tick of the rectangle.
	tick_f	The finishing tick of the rectangle.
	note⊷	The high note of the rectangle.
	_h	

Parameters

	note⊷	The low note of the rectangle.
	_/	
out	х	The destination for the x value in pixels.
out	У	The destination for the y value in pixels.
out	W	The destination for the rectangle width in pixels.
out	h	The destination for the rectangle height value in pixels.

12.65.2.34 void seq64::seqroll::convert_sel_box_to_rect (midipulse tick_s, midipulse tick_f, int note_h, int note_l)

[private]

Parameters

tick_s	The starting tick of the rectangle.
tick_f	The finishing tick of the rectangle.
note⊷ _h	The high note of the rectangle.
note← _I	The low note of the rectangle.

12.65.2.35 void seq64::seqroll::get_selected_box (midipulse & tick_s, int & note_h, midipulse & tick_f, int & note_l) [private]

Parameters

out	tick_s	The starting tick of the rectangle.
out	tick_f	The finishing tick of the rectangle.
out	note⊷	The high note of the rectangle.
	_h	
out	note⊷	The low note of the rectangle.
	_/	

12.65.2.36 void seq64::seqroll::draw_events_on(Glib::RefPtr< Gdk::Drawable > draw) [private]

"Method 0" draws the background sequence, if active. "Method 1" draws the sequence itself.

Parameters

draw	The "drawable" area to draw on.
------	---------------------------------

12.65.2.37 int seq64::seqroll::idle_redraw() [private]

12.65.2.38 int seq64::seqroll::idle_progress() [private]

12.65.2.39 void seq64::seqroll::change_horz() [private]

Roughly similar to seqevent::change_horz().

```
12.65.2.40 void seq64::seqroll::change_vert( ) [private]
12.65.2.41 void seq64::seqroll::move_selection_box(int dx, int dy) [private]
```

We now let the Enter key to finish pasting and deselect the moved notes. With the mouse, selecting all notes, copying them, and moving the selection box, pasting can be completed with either a left-click or the Enter key.

We have a weird problem on our main system where the selection box is very flickery. But it works fine on another system. A Gtk-2 issue? Now it seems to work fine, after an update. No, it seems to work well in sequences that have non-note events amongst the note events.

Parameters

dx	The amount to move the selection box. Values are -1, 0, or 11 is left one snap, 0 is no movement horizontally, and 1 is right one snap.
dy	The amount to move the selection box. Values are -1, 0, or 11 is up one snap, 0 is no movement vertically, and 1 is down one snap.

```
12.65.2.42 void seq64::seqroll::move_selected_notes ( int dx, int dy ) [private]
```

Works with the four arrow keys.

Note that the movement vertically is different for the selection box versus the notes. While the movement values are -1, 0, or 1, the differences are as follows:

```
- Selection box vertical movement:
- -1 is up one note snap.
- 0 is no vertical movement.
- +1 is down one note snap.
- Note vertical movement:
- -1 is down one note.
- 0 is no note vertical movement.
- +1 is up one note.
```

Parameters

dx	The amount to move the selection box or the selection horizontally. Values are -1 (left one time snap), 0
	(no movement), and +1 (right one snap). Obviously values other than +-1 can be used for larger
	movement, but the GUI doesn't yet support that we could implement movement by "pages" some day.
dy	The amount to move the selection box or the selection vertically. See the notes above.

```
12.65.2.43 void seq64::seqroll::grow_selected_notes ( int dx ) [private]
```

Parameters

dx The amount to grow the selection horizontally. Values are -1 (left one time snap), 0 (no stretching), and +1 (right one snap). Obviously values other than +-1 can be used for larger stretching, but the GUI doesn't yet support that.

12.65.2.44 void seq64::seqroll::set_adding (bool adding) [private]

What calls this? It is actually a right click. Not present in the "fruity" implementation. Now moved to the normal seqroll class.

Parameters

adding a note.	adding
----------------	--------

12.65.2.45 void seq64::seqroll::update_mouse_pointer(bool adding = false) [private]

Moved here from the "fruity" seqroll class.

12.65.2.46 bool seq64::seqroll::button_press_initial (GdkEventButton * ev, int & norm_x, int & snapped_x, int & snapped_y) [private]

12.65.2.47 void seq64::seqroll::align_selection (midipulse & tick_s, int & note_h, midipulse & tick_f, int & note_l, int snapped_x) [private]

Save offset that we get from the snap above. Align selection for drawing. Could be used in XRollInput::on_button
_press_event().

12.65.2.48 bool seq64::seqroll::button_press (GdkEventButton * ev) [private]

This function now uses the needs_update flag to determine if the perform object should modify().

Parameters

ev Provides the button-press event to process.

Returns

Returns the value of needs_update. It used to return only true.

12.65.2.49 bool seq64::seqroll::button_release (GdkEventButton * ev) [private]

This function now uses the needs_update flag to determine if the perform object should modify().

Parameters

ev Provides the button-release event to process.

Returns

Returns the value of needs_update. It used to return only true.

If in moving mode, adjust for snap and convert deltas into screen coordinates. Since delta_note was from delta_y, it will be flipped (delta_y[0] = note[127], etc.), so we have to adjust.

A left/middle click converts deltas into screen coordinates, then pushs the undo state. Shift causes a "stretch selected" which currently acts like a "move selected" operation. BUG? Otherwise, Ctrl indirectly allows a "grow selected" operation.

Minor new feature. If the Super (Mod4, Windows) key is pressed when release, keep the adding state in force. One can then use the unadorned left-click key to add notes. Right click to reset the adding mode. This feature is enabled only if allowed by the settings (but is true by default). See the same code in perfrollingut.cpp.

```
12.65.2.50 bool seq64::seqroll::motion_notify ( GdkEventMotion * ev ) [private]
```

We could allow move painting for chords, but that would take some tricky code to move all of the notes of the chord. And allowing painting here currently affects only one note after the chord itself is created.

Parameters

ev Provides the button-release event to process.

Returns

Returns true if the event was processed.

```
12.65.2.51 void seq64::seqroll::clear_selected( ) [inline],[private]
12.65.2.52 void seq64::seqroll::clear_old( ) [inline],[private]
12.65.2.53 void seq64::seqroll::clear_flags( ) [inline],[private]
12.65.2.54 int seq64::seqroll::scroll_offset_x(int x) const [inline],[private]
```

Offsets the x value by the x origin of the current page.

Parameters

```
x The x value to offset.
```

```
12.65.2.55 int seq64::seqroll::scroll_offset_y (int y ) const [inline], [private]
```

Offsets the y value by the y origin of the current page.

Parameters

V	The y value to offset.

12.65.2.56 void seq64::seqroll::set_current_offset_x_y (int x, int y) [inline], [private]


Offsets the current x value by the x origin of the current page.

Parameters

```
x The x value to offset.
```

void set_current_offset_x (int x) { $m_current_x = x + m_scroll_offset_x$; } Useful y calculation. Offsets the current y value by the y origin of the current page.

Parameters



void set_current_offset_y (int y) { m_current_y = $y + m_scroll_offset_y$; } Useful x and y calculation. Offsets the current x and y values by the x and y origin of the current page.

Parameters

X	The y value to offset.
У	The y value to offset.

```
12.65.2.57 bool seq64::seqroll::adding() const [inline], [private]
```

12.65.2.58 bool seq64::seqroll::selecting()const [inline],[private]

12.65.2.59 bool seq64::seqroll::growing () const [inline], [private]

12.65.2.60 bool seq64::seqroll::normal_action() const [inline], [private]

Returns

Returns true if one of those five flags are set.

12.65.2.61 bool seq64::seqroll::select_action() const [inline], [private]

Returns

Returns true if one of those four flags are set.

12.65.2.62 bool seq64::seqroll::drop_action() const [inline], [private]

Returns

Returns true if one of those two flags are set.

```
12.65.2.63 bool seq64::seqroll::moving() const [inline], [private]

12.65.2.64 void seq64::seqroll::on_realize() [private]

12.65.2.65 bool seq64::seqroll::on_expose_event(GdkEventExpose * ev ) [private]
```

Parameters

ev	The expose event to process.
----	------------------------------

Returns

Always returns true.

12.65.2.66 bool seq64::seqroll::on_button_press_event (GdkEventButton * ev) [private]

Parameters

	ev	The expose event to process.	
--	----	------------------------------	--

Returns

Returns the result of the Seq24 interaction or the Fruity interaction, that is, the return value of Seq24Seq \leftarrow RollInput::on_button_press_event() or FruitySeqRollInput::on_button_press_event().

```
12.65.2.67 bool seq64::seqroll::on_button_release_event( GdkEventButton * ev ) [private]
```

This function checks the "rc" interaction-method option, and calls the forwarding function for the seq24 or the fruity interaction method. Might be a good case to prefer inheritance and not try to support changing the interaction method without a restart of Sequencer64.

Parameters

ev	The button release event to process.

Returns

Returns the return value of Seq24SeqRollInput::on_button_release_event() or FruitySeqRollInput::on_ \leftarrow button_release_event().

12.65.2.68 bool seq64::seqroll::on_motion_notify_event (GdkEventMotion * ev) [private]

Parameters

ev The motion-notification event to process.

Returns

Returns the return value of Seq24SeqRollInput::on_motion_notify_event() or FruitySeqRollInput::on_motion ← __notify_event().

12.65.2.69 bool seq64::seqroll::on_focus_in_event(GdkEventFocus *) [private]

Sets the GDK HAS_FOCUS flag. Parameter "ev" is the event-focus event, not used.

Returns

Always returns false.

12.65.2.70 bool seq64::seqroll::on_focus_out_event(GdkEventFocus *) [private]

Resets the GDK HAS_FOCUS flag. Parameter "ev" is the event-focus event, not used.

Returns

Always returns false.

12.65.2.71 bool seq64::seqroll::on_key_press_event(GdkEventKey * ev) [private]

The start/end key may be the same key (i.e. SPACEBAR). Allow toggling when the same key is mapped to both triggers (i.e. SPACEBAR).

Concerning the usage of the arrow keys in this function: This code is reached, but has no visible effect. Why? I think they were meant to move the point for playback. We may have a bug with our new handling of triggers (unlikely), or maybe these depend upon the proper playback mode. In any case, the old functionality is preserved. However, if there are notes selected, then these keys support selection movement.

Since the Up and Down arrow keys are used for movement, we'd have to check selection status before trying to use them to move up and down in the piano roll, in smaller steps than the new Page-Up and Page-Down key support.

Parameters

ev The key-press event to process.

Returns

Returns true if the key-press was handled.

I think we should be able to move and remove notes while playing, which is already supported using the mouse.

```
if (! perf().is_playing)
```

```
12.65.2.72 bool seq64::seqroll::on_scroll_event( GdkEventScroll * ev ) [private]
```

This scroll event only handles basic scrolling without any modifier keys such as the Ctrl or Shift masks. The seqedit class handles that fun stuff.

Note that this function seems to duplicate the functionality of seqkeys::on_scroll_event(). Do we really need both?
Which one do we need?

Parameters

```
ev The scroll event to process.
```

Returns

Returns true if the scroll event was handled.

```
12.65.2.73 void seq64::seqroll::on_size_allocate ( Gtk::Allocation & a ) [private]
```

Calls the base-class version of this function and sets m_window_x and m_window_y to the width and height of the allocation parameter. Then calls update_sizes().

Parameters

```
a The GDK allocation event object.
```

```
12.65.2.74 bool seq64::seqroll::on_leave_notify_event ( GdkEventCrossing * p0 ) [private]
```

Calls m_seqkeys_wid.set_hint_state(false). Parameter "ev" is the event-crossing event, not used.

Returns

Always returns false.

```
12.65.2.75 bool seq64::seqroll::on_enter_notify_event ( GdkEventCrossing * p0 ) [private]
```

 $Calls \ m_seqkeys_wid.set_hint_state(true). \ Parameter "ev" is the event-crossing event, not used.$

Returns

Always returns false.

12.65.3 Friends And Related Function Documentation

```
12.65.3.1 friend class FruitySeqRollInput [friend]
```

We've absorbed the Seq24SeqRollInput class functionality back into seqroll, to save code.

```
12.65.3.2 friend class seqedit [friend]
```

It would be good to be able to avoid this access!

12.65.4 Field Documentation

```
12.65.4.1 Gtk::Adjustment& seq64::seqroll::m_horizontal_adjust [private]
```

12.65.4.2 Gtk::Adjustment& seq64::seqroll::m_vertical_adjust [private]

```
12.65.4.3 rect seq64::seqroll::m_old [private]
```

12.65.4.4 rect seq64::seqroll::m_selected [private]

12.65.4.5 sequence& seq64::seqroll::m_seq [private]

12.65.4.6 seqkeys& seq64::seqroll::m_seqkeys_wid [private]

12.65.4.7 FruitySeqRollInput seq64::seqroll::m_fruity_interaction [private]

```
12.65.4.8 int seq64::seqroll::m_pos [private]
```

Need to clarify what exactly this member is used for.

```
12.65.4.9 int seq64::seqroll::m_zoom [private]
```

12.65.4.10 int seq64::seqroll::m_snap [private]

Same meaning as for the event-bar grid. This value is the denominator of the note size used for the snap.

12.65.4.11 int seq64::seqroll::m_ppqn [private]

Supports values other than the default of 192.

12.65.4.12 int seq64::seqroll::m_note_length [private]

Used in the seq24seqroll module only.

```
12.65.4.13 int seq64::seqroll::m_scale [private]
12.65.4.14 int seq64::seqroll::m_key [private]
12.65.4.15 bool seq64::seqroll::m_adding [private]
This flag was moved from both the fruity and the seq24 seqroll classes.
12.65.4.16 bool seq64::seqroll::m_selecting [private]
12.65.4.17 bool seq64::seqroll::m_moving [private]
12.65.4.18 bool seq64::seqroll::m_moving_init [private]
Used in the fruity and seq24 mouse-handling modules.
12.65.4.19 bool seq64::seqroll::m_growing [private]
12.65.4.20 bool seq64::seqroll::m_painting [private]
Used in the fruity and seq24 mouse-handling modules.
12.65.4.21 bool seq64::seqroll::m_paste [private]
12.65.4.22 bool seq64::seqroll::m_is_drag_pasting [private]
Used in the fruity mouse-handling module.
12.65.4.23 bool seq64::seqroll::m_is_drag_pasting_start [private]
Used in the fruity mouse-handling module.
12.65.4.24 bool seq64::seqroll::m_justselected_one [private]
```

Used in the fruity mouse-handling module.

```
12.65.4.25 int seq64::seqroll::m_move_delta_x [private]
12.65.4.26 int seq64::seqroll::m_move_delta_y [private]
12.65.4.27 int seq64::seqroll::m_move_snap_offset_x [private]
12.65.4.28 int seq64::seqroll::m_progress_x [private]
12.65.4.29 int seq64::seqroll::m_scroll_offset_ticks [private]
12.65.4.30 int seq64::seqroll::m_scroll_offset_key [private]
12.65.4.31 int seq64::seqroll::m_scroll_offset_x [private]
12.65.4.32 int seq64::seqroll::m_scroll_offset_y [private]
12.65.4.33 int seq64::seqroll::m_background_sequence [private]
12.65.4.34 bool seq64::seqroll::m_drawing_background_seq [private]
12.65.4.35 midibyte seq64::seqroll::m_status [private]
```

Used in set_background_sequence(), change_horz(), change_vert(), reset().... Never set to true, except in seq24, let's just comment it out for now. It hasn't been used in sequencer64 for awhile now.

bool m_ignore_redraw; The current status/event selected in the seqedit. Not used in seqroll at present.

```
12.65.4.36 midibyte seq64::seqroll::m_cc [private]
```

Not used in seqroll at present.

12.66 seq64::seqtime Class Reference

This class implements the piano time, whatever that is.

Inheritance diagram for seq64::seqtime:



Public Member Functions

seqtime (sequence &seq, perform &p, int zoom, Gtk::Adjustment &hadjust, int ppqn=SEQ64_USE_DEFA
 ULT_PPQN)

Principal constructor.

• virtual \sim seqtime ()

Let's provide a do-nothing virtual destructor.

· void reset ()

Sets the scroll offset tick and x values, updates the sizes and the pixmap, and resets the window.

· void redraw ()

Very similar to the reset() function, except it doesn't update the sizes.

void set_zoom (int zoom)

Sets the zoom to the given value and resets the window.

Private Member Functions

void draw_pixmap_on_window ()

Draws the pixmap on the window.

- void draw_progress_on_window ()
- void update_pixmap ()

Updates the pixmap.

• void change_horz ()

Changes the scrolling horizontal offset, updates the pixmap, and forces a redraw.

void update sizes ()

Updates the pixmap to a new size and queues up a draw operation.

• bool idle progress ()

Simply returns true.

void on_realize ()

Called when the window is drawn.

bool on expose event (GdkEventExpose *a ev)

Implements the on-expose event handler.

void on_size_allocate (Gtk::Allocation &)

Implements the on-size-allocate event handler.

bool on_button_press_event (GdkEventButton *)

Implements the on-button-press event handler.

bool on_button_release_event (GdkEventButton *)

Implements the on-button-release event handler.

Private Attributes

- sequence & m_seq
- int m scroll offset ticks
- int m_scroll_offset_x
- int m_zoom

one pixel == m_zoom ticks

• int m_ppqn

Additional Inherited Members

12.66.1 Constructor & Destructor Documentation

12.66.1.1 seq64::seqtime::seqtime (sequence & seq, perform & p, int zoom, Gtk::Adjustment & hadjust, int ppqn = SEQ64_USE_DEFAULT_PPQN)

In the constructor you can only allocate colors; get_window() returns 0 because the window is not yet realized>

```
12.66.1.2 virtual seq64::seqtime::~seqtime() [inline], [virtual]

12.66.2 Member Function Documentation

12.66.2.1 void seq64::seqtime::reset()

Basically identical to seqevent::reset().

12.66.2.2 void seq64::seqtime::redraw()

12.66.2.3 void seq64::seqtime::set_zoom(int zoom)

12.66.2.4 void seq64::seqtime::draw_pixmap_on_window() [private]

12.66.2.5 void seq64::seqtime::draw_progress_on_window() [private]
```

When the zoom is at 32 ticks per pixel, there is a thick bar for every measure, and a measure number and major time division every 4 measures.at the default PPQN of 192.

A major line is a line that has a measure number in the timeline. The number of measures in a major line is 1 for zooms from 1:1 to 1:8; 2 for zoom 1:16; 4 for zoom 1:32; 8 for zoom 1:64 (new); and 16 for zoom 1:128. Zooms 1:64 and above look good only for high PPQN values.

We calculate the measure length in 32nd notes. This value is, of course, 32, when the time signature is 4/4. Then calculate measures/line. "measures_per_major" is more like "measures per major line". With a higher zoom than 32, this calculation yields a floating-point exception if m_zoom

32, so we rearrange the calculation and hope that it still works out the

same for smaller values.

Todo Sizing needs to be controlled by font parameters. Instead of 19 or 20, estimate the width of 3 letters. Instead of 9 pixels down, use the height of the seqtime and the height of a character.

```
12.66.2.7 void seq64::seqtime::change_horz( ) [private]
12.66.2.8 void seq64::seqtime::update_sizes( ) [private]
12.66.2.9 bool seq64::seqtime::idle_progress( ) [inline], [private]
12.66.2.10 void seq64::seqtime::on_realize( ) [private]
```

Call the base-class version of this function first. Then addition resources are allocated.

```
12.66.2.12 void seq64::seqtime::on_size_allocate ( Gtk::Allocation & a ) [private]

12.66.2.13 bool seq64::seqtime::on_button_press_event ( GdkEventButton * ) [inline], [private]

Simply returns false.

12.66.2.14 bool seq64::seqtime::on_button_release_event ( GdkEventButton * ) [inline], [private]

Simply returns false.

12.66.3. Field Documentation

12.66.3.1 sequence& seq64::seqtime::m_seq [private]

12.66.3.2 int seq64::seqtime::m_scroll_offset_ticks [private]

12.66.3.3 int seq64::seqtime::m_scroll_offset_x [private]

12.66.3.4 int seq64::seqtime::m_zoom [private]

12.66.3.5 int seq64::seqtime::m_ppqn [private]
```

12.67 seq64::sequence Class Reference

The sequence class is firstly a receptable for a single track of MIDI data read from a MIDI file or edited into a pattern.

Public Types

Public Member Functions

- sequence (int ppqn=SEQ64_USE_DEFAULT_PPQN)
 - Principal constructor.
- ∼sequence ()

A rote destructor.

void partial_assign (const sequence &rhs)

A cut-down version of principal assignment operator.

event_list & events ()

'Getter' function for member m_events

const event_list & events () const

'Getter' function for member m_events

• bool any selected notes () const

 ${\it 'Getter' function for member m_events.any_selected_notes()}$

const triggers::List & triggerlist () const

'Getter' function for member m_triggers This is the const version.

• triggers::List & triggerlist ()

'Getter' function for member m_triggers

· int get_trigger_count () const

Gets the trigger count, useful for exporting a sequence.

- void set trigger paste tick (midipulse tick)
- · midipulse get_trigger_paste_tick () const
- int number () const

'Getter' function for member m_seq_number

void number (int segnum)

'Setter' function for member m_seq_number This setter will set the sequence number only if it has not already been set.

· void modify ()

A convenience function that we have to put here so that the m_parent pointer can be used without an additional include-file in the sequence.hpp module.

• int event_count () const

Returns the number of events stored in m_events.

void set_hold_undo (bool hold)

Modifies the undo-hold container.

• int get_hold_undo () const

'Getter' function for member m_events_undo_hold.count()

void set have undo ()

'Setter' function for member m_have_undo

· bool have_undo () const

'Getter' function for member m have undo

void set_have_redo ()

'Setter' function for member m_have_redo No reliable way to "unmodify" the performance here.

bool have_redo () const

'Getter' function for member m_have_redo

void push_undo (bool hold=false)

Pushes the event-list into the undo-list or the upcoming undo-hold-list.

• void pop_undo ()

If there are items on the undo list, this function pushes the event-list into the redo-list, puts the top of the undo-list into the event-list, pops from the undo-list, calls verify_and_link(), and then calls unselect.

void pop_redo ()

If there are items on the redo list, this function pushes the event-list into the undo-list, puts the top of the redo-list into the event-list, pops from the redo-list, calls verify_and_link(), and then calls unselect.

void push_trigger_undo ()

Calls triggers::push_undo() with locking.

• void pop_trigger_undo ()

Calls triggers::pop_undo() with locking.

- void pop_trigger_redo ()
- void set name (const std::string &name)

Sets the sequence name member, m_name.

void set_name (char *name)

Sets the sequence name member, m name.

- · void set measures (int lengthmeasures)
- int get_measures ()
- int get_ppqn () const

'Getter' function for member m_ppqn Provided as a convenience for the editable_events class.

• void set beats per bar (int beatspermeasure)

'Setter' function for member m_time_beats_per_measure

int get_beats_per_bar () const

'Getter' function for member m_time_beats_per_measure

void set_beat_width (int beatwidth)

'Setter' function for member m time beat width

int get_beat_width () const

'Getter' function for member m_time_beat_width

midipulse measures_to_ticks (int measures=1) const

A convenience function for calculating the number of ticks in the given number of measures.

void clocks_per_metronome (int cpm)

'Setter' function for member m_clocks_per_metronome

int clocks_per_metronome () const

'Getter' function for member m_clocks_per_metronome

void set_32nds_per_quarter (int tpq)

'Setter' function for member m_32nds_per_quarter

• int get_32nds_per_quarter () const

'Getter' function for member m_32nds_per_quarter

void us_per_quarter_note (long upqn)

'Setter' function for member m_us_per_quarter_note

long us_per_quarter_note () const

'Getter' function for member m_us_per_quarter_note

void set rec vol (int rec vol)

'Setter' function for member m_rec_vol If this velocity is greater than zero, then m_note_on_velocity will be set as well.

void set_song_mute (bool mute)

'Setter' function for member m_song_mute This function also calls <u>set_dirty_mp()</u> to make sure that the perfnames panel is updated to show the new mute status of the sequence.

void toggle_song_mute ()

'Setter' function for member m song mute This function toogles the song muting status.

• bool get_song_mute () const

'Getter' function for member m_song_mute

const char * get_name () const

'Getter' function for member m_name pointer

• const std::string & name () const

'Getter' function for member m_name

void set_editing (bool edit)

'Setter' function for member m_editing

• bool get_editing () const

'Getter' function for member m_editing

void set_raise (bool edit)

'Setter' function for member m_raise

· bool get_raise (void) const

'Getter' function for member m_raise

void set_length (midipulse len, bool adjust_triggers=true)

Sets the length (m_length) and adjusts triggers for it, if desired.

· midipulse get length () const

'Getter' function for member m_length

midipulse get_last_tick ()

Returns the last tick played, and is used by the editor's idle function.

· void set last tick (midipulse tick)

'Setter' function for member m_last_tick This function used to be called "set_orig_tick()", now renamed to match up with get_last_tick().

• midipulse mod_last_tick ()

Some MIDI file errors and other things can lead to an m_length of 0, which causes arithmetic errors when m_last_tick is modded against it.

void set playing (bool)

Sets the playing state of this sequence.

• bool get_playing () const

'Getter' function for member m_playing

void toggle_playing ()

Toggles the playing status of this sequence.

void toggle_queued ()

'Setter' function for member m_queued and m_queued_tick Toggles the queued flag and sets the dirty-mp flag.

void off queued ()

'Setter' function for member m_queued Turns off (resets) the queued flag and sets the dirty-mp flag.

void on_queued ()

'Setter' function for member m queued Turns on (sets) the queued flag and sets the dirty-mp flag.

• bool get queued () const

'Getter' function for member m_queued

• midipulse get_queued_tick () const

'Getter' function for member m queued tick

bool check_queued_tick (midipulse tick) const

Helper function for perform.

void set_recording (bool)

'Setter' function for member m_recording and m_notes_on

bool get_recording () const

'Getter' function for member m_recording

void set_snap_tick (int st)

'Setter' function for member m snap tick

void set_quantized_rec (bool qr)

'Setter' function for member m_quantized_rec

• bool get_quantized_rec () const

'Getter' function for member m_quantized_rec

void set_thru (bool)

'Setter' function for member m_thru

• bool get_thru () const

'Getter' function for member m_thru

bool is_dirty_main ()

Returns the value of the dirty main flag, and sets that flag to false (i.e.

bool is_dirty_edit ()

Returns the value of the dirty edit flag, and sets that flag to false.

bool is_dirty_perf ()

Returns the value of the dirty performance flag, and sets that flag to false.

• bool is_dirty_names ()

Returns the value of the dirty names (heh heh) flag, and sets that flag to false.

void set_dirty_mp ()

Sets the dirty flags for names, main, and performance.

void set_dirty ()

Call set_dirty_mp() and then sets the dirty flag for editing.

• midibyte get_midi_channel () const

'Getter' function for member m_midi_channel

bool is_smf_0 () const

Returns true if this sequence is an SMF 0 sequence.

void set_midi_channel (midibyte ch)

Sets the m_midi_channel number.

void print () const

Prints a list of the currently-held events.

void print_triggers () const

Prints a list of the currently-held triggers.

void play (midipulse tick, bool playback_mode)

The play() function dumps notes starting from the given tick, and it pre-buffers ahead.

bool add_event (const event &er)

Adds an event to the internal event list in a sorted manner.

void add_trigger (midipulse tick, midipulse len, midipulse offset=0, bool adjust_offset=true)

Adds a trigger.

void split_trigger (midipulse tick)

Splits a trigger.

• void grow_trigger (midipulse tick_from, midipulse tick_to, midipulse len)

Grows a trigger.

· void del_trigger (midipulse tick)

Deletes a trigger, that brackets the given tick, from the trigger-list.

bool get_trigger_state (midipulse tick)

Checks the list of triggers against the given tick.

bool select_trigger (midipulse tick)

Checks the list of triggers against the given tick.

triggers::List get_triggers () const

Returns a copy of the triggers for this sequence.

• bool unselect_triggers ()

Unselects all triggers.

• bool intersect_triggers (midipulse position, midipulse &start, midipulse &ender)

This function examines each trigger in the trigger list.

• bool intersect_notes (midipulse position, midipulse position_note, midipulse &start, midipulse &ender, int ¬e)

This function examines each note in the event list.

• bool intersect_events (midipulse posstart, midipulse posend, midibyte status, midipulse &start)

This function examines each non-note event in the event list.

void del_selected_trigger ()

Deletes the first selected trigger that is found.

void cut_selected_trigger ()

Copies and deletes the first selected trigger that is found.

void copy_selected_trigger ()

First, this function clears any unpasted middle-click tick setting.

• void paste_trigger (midipulse paste_tick=SEQ64_NO_PASTE_TRIGGER)

If there is a copied trigger, then this function grabs it from the trigger clipboard and adds it.

bool move_selected_triggers_to (midipulse tick, bool adjust_offset, triggers::grow_edit_t which=triggers::G←
 ROW MOVE)

Moves selected triggers as per the given parameters.

• midipulse selected trigger start ()

Gets the last-selected trigger's start tick.

midipulse selected_trigger_end ()

Gets the selected trigger's end tick.

• midipulse get max trigger ()

Get the ending value of the last trigger in the trigger-list.

• void move_triggers (midipulse start_tick, midipulse distance, bool direction)

Moves triggers in the trigger-list.

void copy_triggers (midipulse start_tick, midipulse distance)

Copies triggers to another location.

· void clear_triggers ()

Clears the whole list of triggers.

• midipulse get_trigger_offset () const

'Getter' function for member m_trigger_offset

· void set midi bus (char mb)

Sets the midibus number to dump to.

· char get_midi_bus () const

'Getter' function for member m bus

void set_master_midi_bus (mastermidibus *mmb)

'Setter' function for member m_masterbus Do we need to call set_dirty_mp() here?

• int select_note_events (midipulse tick_s, int note_h, midipulse tick_f, int note_l, select_action_e action)

This function selects events in range of tick start, note high, tick end, and note low.

int select_events (midipulse tick_s, midipulse tick_f, midibyte status, midibyte cc, select_action_e action)

Select all events in the given range, and returns the number selected.

• int select_events (midibyte status, midibyte cc, bool inverse=false)

Select all events with the given status, and returns the number selected.

void select_all_notes (bool inverse=false)

New convenience function.

• int get num selected notes () const

Counts the selected notes in the event list.

• int get_num_selected_events (midibyte status, midibyte cc) const

Counts the selected events, with the given status, in the event list.

void select_all ()

Selects all events, unconditionally.

void copy_selected ()

Copies the selected events.

void cut_selected (bool copyevents=true)

Cuts the selected events.

void paste_selected (midipulse tick, int note)

Pastes the selected notes (and only note events) at the given tick and the given note value.

• void get_selected_box (midipulse &tick_s, int ¬e_h, midipulse &tick_f, int ¬e_l)

Returns the 'box' of the selected items.

• void get_clipboard_box (midipulse &tick_s, int ¬e_h, midipulse &tick_f, int ¬e_l)

Returns the 'box' of the clipboard items.

• midipulse adjust timestamp (midipulse t, bool isnoteoff=false)

A new function to consolidate the adjustment of timestamps in a pattern.

• midipulse clip_timestamp (midipulse ontime, midipulse offtime)

A new function to consolidate the growth/shrinkage of timestamps in a pattern.

void move_selected_notes (midipulse deltatick, int deltanote)

Removes and adds selected notes in position.

void add_note (midipulse tick, midipulse len, int note, bool paint=false)

Adds a note of a given length and note value, at a given tick location.

• void add_event (midipulse tick, midibyte status, midibyte d0, midibyte d1, bool paint=false)

Adds a event of a given status value and data values, at a given tick location.

· bool stream event (event &ev)

Streams the given event.

bool change_event_data_range (midipulse tick_s, midipulse tick_f, midibyte status, midibyte cc, int d_s, int d_f)

Changes the event data range.

void increment_selected (midibyte status, midibyte)

Increments events the match the given status and control values.

· void decrement_selected (midibyte status, midibyte)

Decrements events the match the given status and control values.

void grow_selected (midipulse deltatick)

The original description was "Moves note off event." But this also gets called when simply selecting a second note via a ctrl-left-click, even in seq24.

void stretch selected (midipulse deltatick)

Performs a stretch operation on the selected events.

• bool remove_marked ()

Removes marked events.

bool mark selected ()

Marks the selected events.

void remove selected ()

Removes selected events.

void unpaint_all ()

Unpaints all events in the event-list.

void unselect ()

Deselects all events, unconditionally.

void verify and link ()

This function verifies state: all note-ons have a note-off, and it links note-offs with their note-ons.

void link_new ()

Links a new event.

· void zero_markers ()

Resets everything to zero.

void play note on (int note)

Plays a note from the piano roll on the main bus on the master MIDI buss.

void play_note_off (int note)

Turns off a note from the piano roll on the main bus on the master MIDI buss.

void off_playing_notes ()

Sends a note-off event for all active notes.

• void pause ()

A pause version of reset().

void reset (bool live_mode)

Provides a helper function simplify and speed up perform::reset_sequences().

void reset_draw_marker ()

This refreshes the play marker to the last tick.

void reset_draw_trigger_marker ()

Sets the draw-trigger iterator to the beginning of the trigger list.

draw_type_t get_next_note_event (midipulse *tick_s, midipulse *tick_f, int *note, bool *selected, int *velocity)

Each call to seqdata() fills the passed references with a events elements, and returns true.

• bool get_minmax_note_events (int &lowest, int &highest)

A new function provided so that we can find the minimum and maximum notes with only one (not two) traversal of the event list.

bool get_next_event (midibyte status, midibyte cc, midipulse *tick, midibyte *d0, midibyte *d1, bool *selected)

Get the next event in the event list that matches the given status and control character.

bool get_next_event (midibyte *status, midibyte *cc)

Get the next event in the event list.

• bool get_next_trigger (midipulse *tick_on, midipulse *tick_off, bool *selected, midipulse *tick_offset)

Get the next trigger in the trigger list, and set the parameters based on that trigger.

void quantize_events (midibyte status, midibyte cc, midipulse snap_tick, int divide, bool linked=false)

Grabs the specified events, puts them into a list, quantizes them against the snap ticks, and merges them in to the event container.

· void push quantize (midibyte status, midibyte cc, midipulse snap tick, int divide, bool linked=false)

A new convenience function.

• void transpose_notes (int steps, int scale)

Transposes notes by the given steps, in accordance with the given scale.

· midibyte musical key () const

'Getter' function for member m_musical_key

void musical_key (int key)

'Setter' function for member m musical key

• midibyte musical_scale () const

'Getter' function for member m_musical_scale

• void musical_scale (int scale)

'Setter' function for member m musical scale

· int background_sequence () const

'Getter' function for member m_background_sequence

void background_sequence (int bs)

'Setter' function for member m_background_sequence Only partial validation at present, we do not want the upper limit to be hard-wired at this time.

· void show events () const

A member function to dump a summary of events stored in the event-list of a sequence.

void copy events (const event list &newevents)

Copies an external container of events into the current container, effectively replacing all of its events.

midipulse note_off_margin () const

'Getter' function for member m_note_length

Private Types

typedef std::stack
 event list > EventStack

Provides a stack of event-lists for use with the undo and redo facility.

Private Member Functions

- sequence & operator= (const sequence &rhs)
- bool event_in_range (const event &e, midibyte status, midipulse tick_s, midipulse tick_f) const

A convenience function used a couple of times.

void set_parent (perform *p)

'Setter' function for member m_parent Sets the "parent" of this sequence, so that it can get some extra information about the performance.

void put event on bus (event &ev)

Takes an event that this sequence is holding, and places it on the MIDI buss.

void set_trigger_offset (midipulse trigger_offset)

Sets m_trigger_offset and wraps it to m_length.

void adjust_trigger_offsets_to_length (midipulse newlen)

Adjusts trigger offsets to the length specified for all triggers, and undo triggers.

- · midipulse adjust_offset (midipulse offset)
- void remove (event list::iterator i)

A helper function, which does not lock/unlock, so it is unsafe to call without supplying an iterator from the event-list.

void remove (event &e)

A helper function, which does not lock/unlock, so it is unsafe to call without supplying an iterator from the event-list.

· void remove all ()

Clears all events from the event container.

bool channel_match (const event &e) const

Checks to see if the event's channel matches the sequence's nominal channel.

Private Attributes

• perform * m_parent

For pause support, we need a way for the sequence to find out if JACK transport is active.

· event list m events

This list holds the current pattern/sequence events.

· triggers m triggers

The triggers associated with the sequence, used in the performance/song editor.

event_list m_events_undo_hold

Provides a list of event actions to undo for the Stazed LFO and seqdata support.

· bool m have undo

A stazed flag indicating that we have some undo information.

bool m_have_redo

A stazed flag indicating that we have some redo information.

· EventStack m events undo

Provides a list of event actions to undo.

• EventStack m_events_redo

Provides a list of event actions to redo.

event_list::iterator m_iterator_draw

An iterator for drawing events.

bool m_channel_match

A new feature for recording, based on a "stazed" feature.

· midibyte m midi channel

Contains the proper MIDI channel for this sequence.

midibyte m_bus

Contains the proper MIDI bus number for this sequence.

· bool m song mute

Provides a flag for the song playback mode muting.

• int m_notes_on

Provides a member to hold the polyphonic step-edit note counter.

mastermidibus * m_masterbus

Provides the master MIDI buss which handles the output of the sequence to the proper buss and MIDI channel.

• int m playing notes [SEQ64 MIDI NOTES MAX]

Provides a "map" for Note On events.

bool m_was_playing

Indicates if the sequence was playing.

bool m playing

True if sequence playback currently is in progress for this sequence.

bool m_recording

True if sequence recording currently is in progress for this sequence.

· bool m quantized rec

True if recoring in quantized mode.

bool m_thru

True if recoring in MIDI-through mode.

bool m_queued

True if the events are queued.

· bool m_dirty_main

These flags indicate that the content of the sequence has changed due to recording, editing, performance management, or even (?) a name change.

· bool m_dirty_edit

Provides the main is-edited flag.

· bool m dirty perf

Provides performance dirty flagflag.

• bool m_dirty_names

Provides the names dirtiness flag.

bool m_editing

Indicates that the sequence is currently being edited.

• bool m_raise

Used in segmenu and segedit.

std::string m_name

Provides the name/title for the sequence.

midipulse m_last_tick

These members manage where we are in the playing of this sequence, including triggering.

• midipulse m_queued_tick

Provides the next tick to play?

· midipulse m_trigger_offset

Provides the trigger offset.

const int m_maxbeats

This constant provides the scaling used to calculate the time position in ticks (pulses), based also on the PPQN value.

int m_ppqn

Holds the PPQN value for this sequence, so that we don't have to rely on a global constant value.

int m_seq_number

A new member so that the sequence number is carried along with the sequence.

midipulse m_length

Holds the length of the sequence in pulses (ticks).

midipulse m_snap_tick

The size of snap in units of pulses (ticks).

int m_time_beats_per_measure

Provides the number of beats per bar used in this sequence.

• int m_time_beat_width

Provides with width of a beat.

· int m_clocks_per_metronome

Augments the beats/bar and beat-width with the additional values included in a Time Signature meta event.

• int m_32nds_per_quarter

Augments the beats/bar and beat-width with the additional values included in a Time Signature meta event.

long m_us_per_quarter_note

Augments the beats/bar and beat-width with the additional values included in a Tempo meta event.

• int m rec vol

The volume to be used when recording.

int m_note_on_velocity

The Note On velocity used.

· int m note off velocity

The Note Off velocity used.

midibyte m_musical_key

Holds a copy of the musical key for this sequence, which we now support writing to this sequence.

midibyte m_musical_scale

Holds a copy of the musical scale for this sequence, which we now support writing to this sequence.

· int m background sequence

Holds a copy of the background sequence number for this sequence, which we now support writing to this sequence.

• mutex m_mutex

Provides locking for the sequence.

• const midipulse m_note_off_margin

Provides the number of ticks to shave off of the end of painted notes.

Static Private Attributes

• static event_list m_events_clipboard

A static clipboard for holding pattern/sequence events.

Friends

- · class perform
- · class triggers

12.67.1 Detailed Description

More members than you can shake a stick at.

12.67.2 Member Typedef Documentation

12.67.2.1 typedef std::stack<event_list> seq64::sequence::EventStack [private]

12.67.3 Member Enumeration Documentation

12.67.3.1 enum seq64::sequence::select_action_e

Se the select_note_events() and select_events() functions.

Enumerator

- e_select Selection in progress.
- e_select_one To select a single event.
- e_is_selected The events are selected.
- e_would_select The events would be selected.
- e_deselect To deselect event under the cursor.
- e_toggle_selection Toggle selection under cursor.
- e_remove_one To remove one note under the cursor.

12.67.4 Constructor & Destructor Documentation

12.67.4.1 seq64::sequence::sequence (int ppqn = SEQ64_USE_DEFAULT_PPQN)

ppqn Provides the PPQN parameter to perhaps alter the default PPQN value of this sequence.

```
12.67.4.2 seq64::sequence::\simsequence ( )
```

12.67.5 Member Function Documentation

```
12.67.5.1 sequence& seq64::sequence::operator=( const sequence & rhs ) [private]
```

12.67.5.2 void seq64::sequence::partial_assign (const sequence & rhs)

We're replacing that incomplete function (many members are not assigned) with the more accurately-named partial_assign() function.

It did not assign them all, so we created this partial_assign() function to do this work, and replaced operator =() with this function in client code.

Threadsafe

Parameters

rhs Provides the source of the new member values.

```
12.67.5.3 event_list& seq64::sequence::events() [inline]

12.67.5.4 const event_list& seq64::sequence::events() const [inline]

12.67.5.5 bool seq64::sequence::any_selected_notes() const [inline]

12.67.5.6 const triggers::List& seq64::sequence::triggerlist() const [inline]

12.67.5.7 triggers::List& seq64::sequence::triggerlist() [inline]

12.67.5.8 int seq64::sequence::get_trigger_count() const [inline]

12.67.5.9 void seq64::sequence::set_trigger_paste_tick( midipulse tick) [inline]

12.67.5.10 midipulse seq64::sequence::get_trigger_paste_tick() const [inline]

12.67.5.11 int seq64::sequence::number() const [inline]

12.67.5.12 void seq64::sequence::number(int seqnum) [inline]

12.67.5.13 void seq64::sequence::modify()
```

One minor issue is how can we unmodify the performance? We'd need to keep a count/stack of modifications over all sequences in the performance. Probably not practical.

```
12.67.5.14 int seq64::sequence::event_count() const
```

Note that only playable events are counted in a sequence. If a sequence class function provides a mutex, call m_events.count() instead.

Threadsafe

Returns

Returns m_events.count().

12.67.5.15 void seq64::sequence::set_hold_undo (bool hold)

Parameters

hold

If true, then the events in the m_events container are added to the m_events_undo_hold container. Otherwise, that container is cleared.

```
12.67.5.16 int seq64::sequence::get_hold_undo() const [inline]
12.67.5.17 void seq64::sequence::set_have_undo() [inline]
12.67.5.18 bool seq64::sequence::have_undo() const [inline]
12.67.5.19 void seq64::sequence::set_have_redo() [inline]
12.67.5.20 bool seq64::sequence::have_redo() const [inline]
12.67.5.21 void seq64::sequence::push_undo(bool hold = false)
```

Threadsafe

Parameters

hold A new parameter for the stazed undo/redo support, not yet used. If true, then the events go into the undo-hold-list.

```
12.67.5.22 void seq64::sequence::pop_undo()
```

We would like to be able to set perform's modify flag to false here, but other sequences might still be in a modified state. We could add a modify flag to sequence, and falsify that flag here. Something to think about.

Threadsafe

```
12.67.5.23 void seq64::sequence::pop_redo()
```

```
12.67.5.24 void seq64::sequence::push_trigger_undo()
Threadsafe
12.67.5.25 void seq64::sequence::pop_trigger_undo ( )
12.67.5.26 void seq64::sequence::pop_trigger_redo()
12.67.5.27
           void seq64::sequence::set_name ( const std::string & name )
12.67.5.28
          void seq64::sequence::set_name ( char * name )
12.67.5.29
          void seq64::sequence::set_measures ( int lengthmeasures )
12.67.5.30 int seq64::sequence::get_measures ( )
12.67.5.31 int seq64::sequence::get_ppqn() const [inline]
12.67.5.32 void seq64::sequence::set_beats_per_bar ( int beatspermeasure )
Threadsafe
Parameters
 beatspermeasure
                      The new setting of the beats-per-bar value.
12.67.5.33 int seq64::sequence::get_beats_per_bar( ) const [inline]
12.67.5.34 void seq64::sequence::set_beat_width ( int beatwidth )
Threadsafe
Parameters
 beatwidth
              The new setting of the beat width value.
12.67.5.35 int seq64::sequence::get_beat_width() const [inline]
Threadsafe
12.67.5.36 midipulse seq64::sequence::measures_to_ticks (int measures = 1) const [inline]
```

```
12.67.5.37 void seq64::sequence::clocks_per_metronome(int cpm) [inline]

12.67.5.38 int seq64::sequence::clocks_per_metronome() const [inline]

12.67.5.39 void seq64::sequence::set_32nds_per_quarter(int tpq) [inline]

12.67.5.40 int seq64::sequence::get_32nds_per_quarter() const [inline]

12.67.5.41 void seq64::sequence::us_per_quarter_note(long upqn) [inline]

12.67.5.42 long seq64::sequence::us_per_quarter_note() const [inline]

12.67.5.43 void seq64::sequence::set_rec_vol(int recvol)
```

Threadsafe

Parameters

recvol The new setting of the recording volume setting. It is used only if it ranges from 0 to SEQ64_MAX_NOTE_ON_VELOCITY.

```
12.67.5.44 void seq64::sequence::set_song_mute ( bool mute ) [inline]
12.67.5.45 void seq64::sequence::toggle_song_mute ( ) [inline]
12.67.5.46 bool seq64::sequence::get_song_mute ( ) const [inline]
12.67.5.47 const char* seq64::sequence::get_name ( ) const [inline]
```

Deprecated

```
12.67.5.48 const std::string& seq64::sequence::name() const [inline]
12.67.5.49 void seq64::sequence::set_editing(bool edit) [inline]
12.67.5.50 bool seq64::sequence::get_editing() const [inline]
12.67.5.51 void seq64::sequence::set_raise(bool edit) [inline]
12.67.5.52 bool seq64::sequence::get_raise(void) const [inline]
12.67.5.53 void seq64::sequence::set_length(midipulse len, bool adjust_triggers = true)
```

This function is called in seqedit::apply_length(), when the user selects a sequence length in measures. That function calculates the length in ticks:

```
L = M \times B \times 4 \times P / W
         L == length (ticks or pulses)
         {\tt M} == {\tt number} \ {\tt of} \ {\tt measures}
         B == beats per measure
         P == pulses per quarter-note
         W == beat width in beats per measure
For our "b4uacuse" MIDI file, M can be about 100 measures, B is 4,
P can be 192 (but we want to support higher values), and W is 4.
So L = 100 * 4 * 4 * 192 / 4 = 76800 ticks. Seems small.
Threadsafe
12.67.5.54 midipulse seq64::sequence::get_length() const [inline]
12.67.5.55 midipulse seq64::sequence::get_last_tick()
If m_length is 0, this function returns m_last_tick - m_trigger_offset, to avoid an arithmetic exception. Should we
return 0 instead?
Note that seqroll calls this function to help get the location of the progress bar. What does perfedit do?
12.67.5.56 void seq64::sequence::set_last_tick ( midipulse tick )
```

Threadsafe

```
12.67.5.57 midipulse seq64::sequence::mod_last_tick( ) [inline]
```

This function replaces the "m_last_tick % m_length", returning m_last_tick if m_length is 0 or 1.

```
12.67.5.58 void seq64::sequence::set_playing (bool p)
```

When playing, and the sequencer is running, notes get dumped to the ALSA buffers.

Parameters

p Provides the playing status to set. True means to turn on the playing, false means to turn it off, and turn off any notes still playing.

```
12.67.5.59 bool seq64::sequence::get_playing( ) const [inline]
12.67.5.60 void seq64::sequence::toggle_playing( ) [inline]
```

How exactly does this differ from toggling the mute status?

```
12.67.5.61 void seq64::sequence::toggle_queued()
Also calculates the queued tick based on m_last_tick.
Threadsafe
12.67.5.62 void seq64::sequence::off_queued()
Do we need to set m_queued_tick as in toggle_queued()? Currently not used.
Threadsafe
12.67.5.63 void seq64::sequence::on_queued()
Do we need to set m_queued_tick as in toggle_queued()? Currently not used.
Threadsafe
12.67.5.64 bool seq64::sequence::get_queued( ) const [inline]
12.67.5.65 midipulse seq64::sequence::get_queued_tick( ) const [inline]
12.67.5.66 bool seq64::sequence::check_queued_tick ( midipulse tick ) const [inline]
12.67.5.67 void seq64::sequence::set_recording ( bool r )
Threadsafe
12.67.5.68 bool seq64::sequence::get_recording( ) const [inline]
12.67.5.69 void seq64::sequence::set_snap_tick ( int st )
Threadsafe
12.67.5.70 void seq64::sequence::set_quantized_rec ( bool qr )
Threadsafe
12.67.5.71 bool seq64::sequence::get_quantized_rec( ) const [inline]
12.67.5.72 void seq64::sequence::set_thru ( bool r )
Threadsafe
```

Not threadsafe

```
12.67.5.73 bool seq64::sequence::get_thru() const [inline]
12.67.5.74 bool seq64::sequence::is_dirty_main()
resets it). This flag signals that a redraw is needed from recording.
Threadsafe
Returns
      Returns the dirty status.
12.67.5.75 bool seq64::sequence::is_dirty_edit( )
The m_dirty_edit flag is set by the function set_dirty().
Threadsafe
Returns
      Returns the dirty status.
12.67.5.76 bool seq64::sequence::is_dirty_perf()
Threadsafe
Returns
      Returns the dirty status.
12.67.5.77 bool seq64::sequence::is_dirty_names ( )
Not sure that we need to lock a boolean on modern processors.
Threadsafe
Returns
      Returns the dirty status.
12.67.5.78 void seq64::sequence::set_dirty_mp ( )
These flags are meant for causing user-interface refreshes, not for performance modification.
m_dirty_names is set to false in is_dirty_names(); m_dirty_names is set to false in is_dirty_main(); m_dirty_names
is set to false in is_dirty_perf().
```

12.67.5.79 void seq64::sequence::set_dirty ()

Threadsafe

12.67.5.80 midibyte seq64::sequence::get_midi_channel() const [inline]

12.67.5.81 bool seq64::sequence::is_smf_0() const [inline]

12.67.5.82 void seq64::sequence::set_midi_channel (midibyte ch)

Threadsafe

12.67.5.83 void seq64::sequence::print () const

Not threadsafe

12.67.5.84 void seq64::sequence::print_triggers () const

Not threadsafe

12.67.5.85 void seq64::sequence::play (midipulse tick, bool playback_mode)

This function is called by the sequencer thread, performance. The tick comes in as global tick.

It turns the sequence off after we play in this frame.

Note

With pause support, the progress bar for the pattern/sequence editor does what we want: pause with the pause button, and rewind with the stop button. Works with JACK, with issues, but we'd like to have the stop button do a rewind in JACK, too.

Parameters

tick	Provides the current end-tick value.
playback_mode	Provides how playback is managed. True indicates that it is performance/song-editor
	playback, controlled by the set of patterns and triggers set up in that editor, and saved with
	the song in seq24 format. False indicates that the playback is controlled by the main
	windows, in live mode.

Threadsafe

12.67.5.86 bool seq64::sequence::add_event (const event & er)

Then it reset the draw-marker and sets the dirty flag.

Currently, when reading a MIDI file [see the midifile::parse() function], only the main events (notes, after-touch, pitch, program changes, etc.) are added with this function. So, we can rely on reading only playable events into a sequence. Well, actually, certain meta-events are also read, to obtain channel, buss, and more settings. Also read for a sequence, if the global-sequence flag is not set, are the new key, scale, and background sequence parameters.

This module (sequencer) adds all of those events as well, but it can surely add other events. We should assume that any events added by sequencer are playable/usable.

Here, we could ignore events not on the sequence's channel, as an option. We have to be careful because this function can be used in painting events.

Threadsafe

Warning

This pushing (and, in writing the MIDI file, the popping), causes events with identical timestamps to be written in reverse order. Doesn't affect functionality, but it's puzzling until one understands what is happening. Actually, this is true only in Seq24, we've fixed that behavior for Sequencer64.

Parameters

To the control of the count to be added, the count is copied into the counts contained	er	Provide a reference to the event to be added; the event is copied into the events container.
--	----	--

Returns

Returns true if the event was added.

12.67.5.87 void seq64::sequence::add_trigger (midipulse *tick*, midipulse *len*, midipulse *offset* = 0, bool *fixoffset* = true)

A pass-through function that calls triggers::add(). See that function for more details.

Threadsafe

Parameters

tick	The time destination of the trigger.
len	The duration of the trigger.
offset	The performance offset of the trigger.
fixoffset	If true, adjust the offset.

12.67.5.88 void seq64::sequence::split_trigger (midipulse splittick)

This is the public overload of split trigger.

Threadsafe

Parameters

splittick	The time location of the split.
-----------	---------------------------------

12.67.5.89 void seq64::sequence::grow_trigger (midipulse tickfrom, midipulse tickto, midipulse len)

See triggers::grow() for more information.

Parameters

tickfrom	The desired from-value back which to expand the trigger, if necessary.
tickto	The desired to-value towards which to expand the trigger, if necessary.
len	The additional length to append to tickto for the check.

Threadsafe

12.67.5.90 void seq64::sequence::del_trigger (midipulse tick)

See triggers::remove().

Threadsafe

Parameters

tick Provides the tick to be used for finding	the trigger to be erased.
---	---------------------------

12.67.5.91 bool seq64::sequence::get_trigger_state (midipulse tick)

If any trigger is found to bracket that tick, then true is returned.

Parameters

tick Provides the tick of interest	Provides the tick of interest.
------------------------------------	--------------------------------

Returns

Returns true if a trigger is found that brackets the given tick.

12.67.5.92 bool seq64::sequence::select_trigger (midipulse tick)

If any trigger is found to bracket that tick, then true is returned, and the trigger is marked as selected.

Parameters

tick Provides the tick of in	terest.
------------------------------	---------

Returns

Returns true if a trigger is found that brackets the given tick; this is the return value of m_triggers.select().

12.67.5.93 triggers::List seq64::sequence::get_triggers () const

This function is basically a threadsafe version of sequence::triggerlist().

Returns

Returns of copy of m triggers.triggerlist().

12.67.5.94 bool seq64::sequence::unselect_triggers ()

Returns

Returns the m_triggers.unselect() return value.

12.67.5.95 bool seq64::sequence::intersect_triggers (midipulse position, midipulse & start, midipulse & ender)

If the given position is between the current trigger's tick-start and tick-end values, the these values are copied to the start and end parameters, respectively, and then we exit. See triggers::intersect().

Threadsafe

Parameters

position	The position to examine.
start	The destination for the starting tick of the matching trigger.
ender	The destination for the ending tick of the matching trigger.

Returns

Returns true if a trigger was found whose start/end ticks contained the position. Otherwise, false is returned, and the start and end return parameters should not be used.

12.67.5.96 bool seq64::sequence::intersect_notes (midipulse position, midipulse position_note, midipulse & start, midipulse & ender, int & note)

If the given position is between the current notes on and off time values, values, the these values are copied to the start and end parameters, respectively, the note value is copied to the note parameter, and then we exit.

Threadsafe

Parameters

	position	The position to examine.
	position_note	I think this is the note value we might be looking for ???
out	start	The destination for the starting timestamp of the matching note.
out	ender	The destination for the ending timestamp of the matching note.
out	note	The destination for the note of the matching event. Why is this an int value???

Returns

Returns true if a event was found whose start/end ticks contained the position. Otherwise, false is returned, and the start and end return parameters should not be used.

12.67.5.97 bool seq64::sequence::intersect_events (midipulse *posstart*, midipulse *posend*, midibyte *status*, midipulse & *start*)

If the given position is between the current notes's timestamp-start and timestamp-end values, the these values are copied to the posstart and posend parameters, respectively, and then we exit.

Threadsafe

Parameters

posstart	The starting position to examine.
posend	The ending position to examine.
status	The desired status value.
start	The destination for the starting timestamp of the matching trigger.

Returns

Returns true if a event was found whose start/end timestamps contained the position. Otherwise, false is returned, and the start and end return parameters should not be used.

```
12.67.5.98 void seq64::sequence::del_selected_trigger ( )
```

12.67.5.99 void seq64::sequence::cut_selected_trigger()

12.67.5.100 void seq64::sequence::copy_selected_trigger()

Then it copies the first selected trigger that is found.

12.67.5.101 void seq64::sequence::paste_trigger (midipulse paste_tick = SEQ64_NO_PASTE_TRIGGER)

Why isn't this protected by a mutex? We will enable this if anything bad happens, such as a deadlock, or corruption, that we can prove happens here.

Parameters

paste_tick	A new parameter that provides the tick for pasting, or SEQ64_NO_PASTE_TRIGGER (-1) if there
	is none.

12.67.5.102 bool seq64::sequence::move_selected_triggers_to (midipulse tick, bool adjustoffset, triggers::grow_edit_t which = triggers::GROW_MOVE)

min_tick][0 1][max_tick

2

```
The \a which parameter has three possible values:

-# If we are moving the 0, use first as offset.

-# If we are moving the 1, use the last as the offset.

-# If we are moving both (2), use first as offset.
```

Threadsafe

Parameters

tick	The tick at which the trigger starts.
adjustoffset	Set to true if the offset is to be adjusted.
which	Selects which movement will be done, as discussed above.

Returns

Returns the value of triggers::move_selected(), which indicate that the movement could be made. Used in Seq24PerfInput::handle motion key().

12.67.5.103 midipulse seq64::sequence::selected_trigger_start()

Threadsafe

Returns

Returns the tick_start() value of the last-selected trigger. If no triggers are selected, then -1 is returned.

12.67.5.104 midipulse seq64::sequence::selected_trigger_end ()

Threadsafe

Returns

Returns the tick_end() value of the last-selected trigger. If no triggers are selected, then -1 is returned.

12.67.5.105 midipulse seq64::sequence::get_max_trigger()

Threadsafe

Returns

Returns the maximum trigger value.

12.67.5.106 void seq64::sequence::move_triggers (midipulse starttick, midipulse distance, bool direction)

Note the dependence on the m_length member being kept in sync with the parent's value of m_length.

	starttick	Starttick The current location of the triggers.	
distance The distance away from the current location to which to move the triggers		The distance away from the current location to which to move the triggers.	
	direction	If true, the triggers are moved forward. If false, the triggers are moved backward.	

12.67.5.107 void seq64::sequence::copy_triggers (midipulse starttick, midipulse distance)

Threadsafe

Parameters

starttick	The current location of the triggers.
distance	The distance away from the current location to which to copy the triggers.

12.67.5.108 void seq64::sequence::clear_triggers ()

Threadsafe

12.67.5.109 midipulse seq64::sequence::get_trigger_offset() const [inline]

12.67.5.110 void seq64::sequence::set_midi_bus (char mb)

Threadsafe

12.67.5.111 char seq64::sequence::get_midi_bus() const [inline]

12.67.5.112 void seq64::sequence::set_master_midi_bus (mastermidibus * mmb)

Threadsafe

Parameters

mmb Provides a pointer to the master MIDI buss for this sequence. This should be a reference, but isn't, nor is it checked.

12.67.5.113 int seq64::sequence::select_note_events (midipulse *tick_s*, int *note_h*, midipulse *tick_f*, int *note_l*, select_action_e *action*)

Returns the number selected.

Compare this function to the convenience function select_all_notes(), which doesn't use range information.

tick_s	The start time of the selection.		
note⊷	The high note of the selection.		
_h			
tick_f	The finish time of the selection.		
note⊷	The low note of the selection.		
_/			
action	The action to perform, one of e_select, e_select_one, e_is_selected, e_would_select, e_deselect,		
	e_toggle_selection, and e_remove_one.		

Returns

Returns the number of events acted on, or 0 if no desired event was found.

12.67.5.114 int seq64::sequence::select_events (midipulse tick_s, midipulse tick_f, midibyte status, midibyte cc, select_action_e action)

Note that there is also an overloaded version of this function.

Threadsafe

Parameters

tick⊷	The start time of the selection.	
_s		
tick⊷	The finish time of the selection.	
_f		
status	The desired event in the selection.	
СС	The desired control-change in the selection, if the event is a control-change.	
action The desired selection action.		

Returns

Returns the number of events selected.

12.67.5.115 int seq64::sequence::select_events (midibyte status, midibyte cc, bool inverse = false)

Note that there is also an overloaded version of this function.

Threadsafe

Warning

This used to be a void function, so it just returns 0 for now.

status	Provides the status value to be selected.	
СС	If the status is EVENT_CONTROL_CHANGE, then data byte 0 must match this value.	
inverse	If true, invert the selection.	

Returns

Always returns 0.

12.67.5.116 void seq64::sequence::select_all_notes (bool inverse = false) [inline]

What about Aftertouch events? I think we need to select them as well in seqedit, so let's add that selection here as well.

Parameters

inverse	If set to true (the default is false), then this causes the selection to be inverted.
---------	---

12.67.5.117 int seq64::sequence::get_num_selected_notes () const

Threadsafe

Returns

Returns m_events.count_selected_notes().

12.67.5.118 int seq64::sequence::get_num_selected_events (midibyte status, midibyte cc) const

If the event is a control change (CC), then it must also match the given CC value.

Threadsafe

Parameters

status	The desired kind of event to count.	
СС	The desired control-change to count, if the event is a control-change.	

Returns

Returns m_events.count_selected_events().

12.67.5.119 void seq64::sequence::select_all()

```
12.67.5.120 void seq64::sequence::copy_selected ( )
```

This function also has the danger, discovered by user 0rel, of events being modified after being added to the clipboard. So we add his reconstruction fix here as well. To summarize the steps:

```
-# Clear the m_events_clipboard.
-# Add all selected events in this clipboard to the sequence.
-# Normalize the timestamps of the events in the clip relative to the timestamp of the first selected event. (Is this really needed?)
-# Reconstruct/reconstitute the m_events_clipboard.
```

This process is a bit easier to manage than erase/insert on events because std::multimap has no erase() function that returns the next valid iterator. Also, we use a local clipboard first, to save on copying. We've enhanced the error-checking, too.

Finally, note that m events clipboard is a static member of sequence, so:

```
-# Copying can be done between sequences.
-# Access to it needs to be protected by a mutex.
```

Threadsafe

```
12.67.5.121 void seq64::sequence::cut_selected ( bool copyevents = true )
```

Pushes onto the undo stack, may copy the events, marks the selected events, and removes them. Now also sets the dirty flag so that the caller doesn't have to. Also raises the modify flag on the parent perform object.

Threadsafe

Parameters

copyevents	If true, copy the selected events before marking and removing them.

12.67.5.122 void seq64::sequence::paste_selected (midipulse tick, int note)

Also, we've moved external calls to push_undo() into this function. The caller shouldn't have to do that.

The event_keys used to access/sort the multimap event_list is not updated after changing timestamp/rank of the stored events. Regenerating all key/value pairs before merging them solves this issue, so that the order of events in the sequence will be preserved. This action is not needed for moving or growing events. Nor is it needed if the old std::list implementation of the event container is compiled in. However, it is needed in any operation that modifies the timestamp of an event inside the container:

```
- copy_selected()
- paste_selected()
- quantize_events() TODO TODO!
```

The alternative to reconstructing the map is to erase-and-insert the events modified in the code above, rather than just tweaking their values, which have an effect on sorting for the event-map implementation. However, multimap does not provide an erase() function that returns the next valid iterator, which would complicate this method of operation. So we're inclined to stick with this solution.

There was an issue with copy/pasting a whole sequence. The pasted events did not go to their destination, but overlayed the original events. This bugs also occurred in Seq24 0.9.2. It occurs with the allofarow.mid file when doing Ctrl-A Ctrl-C Ctrl-V Move-Mouse Left-Click. It turns out the original code was checking only the first event to see if it was a Note event. For sequences that started with a Control Change or Program Change (or other non-Note events), the highest note was never modified, and none of the note events were adjusted.

Finally, we only want to transpose note events (i.e. alter m_data[0]), and not other kinds of events. We still need to figure out what to do with aftertouch, though. Currently likely to be covered by the processing of the note that it accompanies.

Threadsafe

Parameters

tick	The time destination for the paste. This represents the "x" coordinate of the upper left corner of the paste-box. It will be converted to an offset, for example pasting every event 48 ticks forward from the original copy.
note	The note/pitch destination for the paste. This represents the "y" coordinate of the upper left corner of the paste-box. It will be converted to an offset, for example pasting every event 7 notes higher than the original copy.

12.67.5.123 void seq64::sequence::get_selected_box (midipulse & tick_s, int & note_h, midipulse & tick_f, int & note_l)

Note the common-code betweem this function and <code>get_clipboard_box()</code>. Also note we could return a boolean indicating if the return values were filled in.

Threadsafe

Parameters

out	tick_s	Side-effect return reference for the start time.
out	note⊷	Side-effect return reference for the high note.
	_h	
out	tick_f	Side-effect return reference for the finish time.
out	note⊷	Side-effect return reference for the low note.
	_/	

12.67.5.124 void seq64::sequence::get_clipboard_box (midipulse & tick_s, int & note_h, midipulse & tick_f, int & note_l)

Note the common-code betweem this function and get_selected_box(). Also note we could return a boolean indicating if the return values were filled in.

Threadsafe

Parameters

out	tick_s	Side-effect return reference for the start time.
out	note⊷	Side-effect return reference for the high note.
	_h	
out	tick_f	Side-effect return reference for the finish time.
out	note⊷	Side-effect return reference for the low note.
	_1	

12.67.5.125 midipulse seq64::sequence::adjust_timestamp (midipulse t, bool isnoteoff = false)

If the timestamp is greater that m_length, we do round robin magic. Taken from similar code in move_selected_← notes() and grow_selected(). Be careful using this function.

Parameters

t	Provides the timestamp to be adjusted based on m_length.
isnoteoff	Used for "expanding" the timestamp from 0 to just less than m_length, if necessary. Should be set
	to true only for Note Off events; it defaults to false, which means to wrap the events around the end
	of the sequence if necessary, and is used only in movement, not in growth.

Returns

Returns the adjusted timestamp.

12.67.5.126 midipulse seq64::sequence::clip_timestamp (midipulse ontime, midipulse offtime)

If the new (off) timestamp is less than the on-time, it is clipped to the snap value. If it is greater than the length of the sequence, then it is clipped to the sequence length. No wrap-around.

Parameters

ontime	Provides the original time, which limits the amount of negative adjustment that can be done.
offtime	Provides the timestamp to be adjusted and clipped.

Returns

Returns the adjusted timestamp.

12.67.5.127 void seq64::sequence::move_selected_notes (midipulse delta_tick, int delta_note)

Also currently moves any other events in the range of the selection.

Also, we've moved external calls to push_undo() into this function. The caller shouldn't have to do that.

Another thing this function does is wrap-around when movement occurs. Any events (except Note Off) that will start just after the END of the pattern will be wrapped around to the beginning of the pattern.

Fixed:

Select all notes in a short pattern that starts at time 0 and has non-note events starting at time 0 (see contrib/midi/allofarow.mid); move them with the right arrow, and move them back with the left arrow; then view in the event editor, and see that the non-Note events have not moved back, and in fact move way too far to the right, actually to near the END marker. We've fixed that in the new adjust_timestamp() function.

This function checks for any marked events in seq24, but now we make sure the event is a Note On or Note Off event before dealing with it. We now handle properly events like Program Change, Control Change, and Pitch Wheel. Remember that Aftertouch is treated like a note, as it has velocity. For non-Notes, event::get_note() returns m_data[0], and we don't want to adjust that.

delta_tick	Provides the amount of time to move the selected notes. Note that it also applies to events. Note-Off events are expanded to m_length if their timestamp would be 0. All other events will wrap around to 0.
delta_note	Provides the amount of pitch to move the selected notes. This value is applied only to Note (On and Off) events. Also, if this value would bring a note outside the range of 0 to 127, that note is not changed and the event is not moved.

12.67.5.128 void seq64::sequence::add_note (midipulse tick, midipulse len, int note, bool paint = false)

It adds a single note-on / note-off pair.

The paint parameter indicates if we care about the painted event, so then the function runs though the events and deletes the painted ones that overlap the ones we want to add.

Also note that push undo() is not incorporated into this function, for the sake of speed.

Here, we could ignore events not on the sequence's channel, as an option. We have to be careful because this function can be used in painting notes.

Stazed:

http://www.blitter.com/~russtopia/MIDI/~jglatt/tech/midispec.htm

Note Off: The first data is the note number. There are 128 possible notes on a MIDI device, numbered 0 to 127 (where Middle C is note number 60). This indicates which note should be released. The second data byte is the velocity, a value from 0 to 127. This indicates how quickly the note should be released (where 127 is the fastest). It's up to a MIDI device how it uses velocity information. Often velocity will be used to tailor the VCA release time. MIDI devices that can generate Note Off messages, but don't implement velocity features, will transmit Note Off messages with a preset velocity of 64.

Also, we now see that seq24 never used the recording-velocity member (m_rec_vol). We use it to modify the new m note on velocity member if the user changes it in the seqedit window.

Threadsafe

Parameters

tick	The time destination of the new note, in pulses.	
len	The duration of the new note, in pulses.	
note	The pitch destination of the new note.	
paint	If true, repaint the whole set of events, in order to be left with a clean view of the inserted event. The	
	default is false.	

12.67.5.129 void seq64::sequence::add_event (midipulse *tick*, midibyte *status*, midibyte *d0*, midibyte *d1*, bool *paint* = false)

The paint parameter indicates if we care about the painted event, so then the function runs though the events and deletes the painted ones that overlap the ones we want to add.

Threadsafe

Parameters

tick	The time destination of the event.	
status	The type of event to add.	
d0	The first data byte for the event.	
d1	The second data byte for the event (if needed).	
paint If true, the inserted event is marked for paint		

12.67.5.130 bool seq64::sequence::stream_event (event & ev)

The event's timestamp is adjusted, if needed. If recording:

```
If the pattern is playing, the event is added.
If the pattern is playing and quantized record is in force, the note's timestamp is altered.
If not playing, but the event is a Note On or Note Off, we add it and keep track of it.
```

If MIDI Thru is enabled, the event is put on the buss.

We are adding a feature where events are rejected if their channel doesn't match that of the sequence. This has been a complaint of some people. Could modify the add_event()) and add_note()) functions, but better to do it here for comprehensive event support. Also have to make sure the event-channel is preserved before this function is called, and also need to make sure that the channel is appended on both playback and in saving of the MIDI file.

We are also adding the usage, at last, of the m_rec_vol member.

Todo When we feel like debugging, we will replace the global is-playing call with the parent perform's is-running call.

Threadsafe

Parameters

	ev	Provides the event to stream.
ı	0.	i rovidoo trio ovorit to otrodiri.

Returns

Returns true if the event's channel matched that of this sequence, and the channel-matching feature was set to true. Also returns true if we're not using channel-matching. A return value of true means the event should be saved.

12.67.5.131 bool seq64::sequence::change_event_data_range (midipulse tick_s, midipulse tick_f, midibyte status, midibyte cc, int data_s, int data_f)

Changes only selected events, if any.

Threadsafe

Let t == the current tick value; ts == tick start value; tf == tick finish value; ds = data start value; df == data finish value; d = the new data value. Then

If this were an interpolation formula it would be:

Something is not quite right; to be investigated.

Parameters

tick⊷	Provides the starting tick value.
_s	
tick⊷	Provides the ending tick value.
_f	
status	Provides the event status that is to be changed.
СС	Provides the event control value.
data⊷	Provides the starting data value.
_s	
data⇔	Provides the finishing data value.
_f	

Returns

Returns true if the data was changed.

12.67.5.132 void seq64::sequence::increment_selected (midibyte astat, midibyte)

The supported statuses are:

- EVENT_NOTE_ON
- EVENT_NOTE_OFF
- EVENT_AFTERTOUCH
- EVENT_CONTROL_CHANGE EVENT_PITCH_WHEEL
- EVENT_PROGRAM_CHANGE
- EVENT_CHANNEL_PRESSURE

Threadsafe

Parameters

Parameter "acontrol", the desired control-change, is unused. This might be a bug, or at least a missing feature.

12.67.5.133 void seg64::sequence::decrement_selected (midibyte astat, midibyte)

The supported statuses are:

- · One-byte messages
 - EVENT PROGRAM CHANGE
 - EVENT_CHANNEL_PRESSURE
- Two-byte messages
 - EVENT NOTE ON
 - EVENT_NOTE_OFF
 - EVENT AFTERTOUCH
 - EVENT_CONTROL_CHANGE
 - EVENT_PITCH_WHEEL

Threadsafe

Parameters

Parameter "acontrol", the desired control-change, is unused. This might be a bug, or at least a missing feature.

12.67.5.134 void seq64::sequence::grow_selected (midipulse delta_tick)

And, though it doesn't move Note Off events, it does reconstruct them.

This function is called when doing a ctrl-left mouse move on the selected notes or when using ctrl-left-arrow or ctrl-right-arrow to shrink or stretch the selected notes. Using the mouse allows pretty much any amount of growth or shrinkage, but use the arrow keys limits the changes to the current snap value.

This function grows/shrinks only Note On events that are marked and linked. If an event is not linked, this function now ignores the event's timestamp, rather than risk a segfault on a null pointer. Compare this function to the stretch_selected() and move_selected_notes() functions.

This function would strip out non-Notes, but now it at least preserves them and moves them, to try to preserve their relative position re the notes.

In any case, we want to mark the original off-event for deletion, otherwise we get duplicate off events, for example in the "Begin/End" pattern in the test.midi file.

This function now tries to prevent pathological growth, such as trying to shrink the notes to zero length or less, or stretch them beyond the length of the sequence. Otherwise we get weird and unexpected results.

Also, we've moved external calls to push_undo() into this function. The caller shouldn't have to do that.

A comment on terminology: The user "selects" notes, while the sequencer "marks" notes. The first thing this function does is mark all the selected notes.

delta_tick	An offset for each linked event's timestamp.
------------	--

12.67.5.135 void seq64::sequence::stretch_selected (midipulse delta_tick)

This should move a note off event, according to old comments, but it doesn't seem to do that. See the grow_\circ
selected() function. Rather, it moves any event in the selection.

Also, we've moved external calls to push undo() into this function. The caller shouldn't have to do that.

Threadsafe

Parameters

delta_tick	Provides the amount of time to stretch the selected notes.
------------	--

```
12.67.5.136 bool seq64::sequence::remove_marked ( )
```

Note how this function forwards the call to m_event.remove_marked().

Threadsafe

Returns

Returns true if at least one event was removed.

```
12.67.5.137 bool seq64::sequence::mark_selected ( )
```

Threadsafe

Returns

Returns true if there were any events that got marked.

```
12.67.5.138 void seq64::sequence::remove_selected ( )
```

This is a new convenience function to fold in the push_undo() and mark_selected() calls. It makes the process slightly faster, as well.

Threadsafe Also makes the whole process threadsafe.

```
12.67.5.139 void seq64::sequence::unpaint_all()
```

```
12.67.5.140 void seq64::sequence::unselect ( )
Threadsafe
12.67.5.141 void seq64::sequence::verify_and_link()
Threadsafe
12.67.5.142 void seq64::sequence::link_new ( )
Threadsafe
12.67.5.143 void seq64::sequence::zero_markers() [inline]
This function is used when the sequencer stops. This function currently sets m_last_tick = 0, but we would like to
avoid that if doing a pause, rather than a stop, of playback. However, commenting out this setting doesn't have any
effect that we can see with a quick look at the user-interface.
12.67.5.144 void seq64::sequence::play_note_on (int note)
It flushes a note to the midibus to preview its sound, used by the virtual piano.
Threadsafe
Parameters
         The note to play. It is not checked for range validity, for the sake of speed.
12.67.5.145 void seq64::sequence::play_note_off ( int note )
Threadsafe
Parameters
         The note to turn off. It is not checked for range validity, for the sake of speed.
12.67.5.146 void seq64::sequence::off_playing_notes ( )
```

Threadsafe

This function does not bother checking if m_masterbus is a null pointer.

```
12.67.5.147 void seq64::sequence::pause ( )
```

The reset() function is currently not called when pausing, but we still need the note-shutoff capability to prevent notes from lingering. Not that we do not call set_playing(false)... it disarms the sequence, which we do not want upon pausing.

```
12.67.5.148 void seq64::sequence::reset ( bool live_mode )
```

Note that, in live mode, the user controls playback, while otherwise JACK or the performance/song editor controls playback. (We're still a bit confounded about these modes, alas.)

Parameters

	live_mode	True if live mode is on.	This means that JACK transport is not in control of playback.	1
--	-----------	--------------------------	---	---

```
12.67.5.149 void seq64::sequence::reset_draw_marker( )
```

It resets the draw marker so that calls to get_next_note_event() will start from the first event.

Threadsafe

```
12.67.5.150 void seq64::sequence::reset_draw_trigger_marker()
```

Threadsafe

```
12.67.5.151 draw_type_t seq64::sequence::get_next_note_event ( midipulse * tick_s, midipulse * tick_f, int * note, bool * selected, int * velocity )
```

When it has no more events, returns a false.

Parameters

out	tick_s	Provides a pointer destination for the start time.	
out	tick_f	Provides a pointer destination for the finish time.	
out	note	Provides a pointer destination for the note pitch value Probably should be a midibyte value.	
out	selected	Provides a pointer destination for the selection status of the note.	
out	velocity	Provides a pointer destination for the note velocity. Probably should be a midibyte value.	

12.67.5.152 bool seq64::sequence::get_minmax_note_events (int & lowest, int & highest)

Todo For efficency, we should calculate this only when the event set changes, and save the results and return them if good.

lowest	A reference parameter to return the note with the lowest value. if there are no notes, then it is set to	
	SEQ64_MIDI_COUNT_MAX-1.	
highest	A reference parameter to return the note with the highest value. if there are no notes, then it is set to -1.	

Returns

If there are no notes in the list, then false is returned, and the results should be disregarded.

12.67.5.153 bool seq64::sequence::get_next_event (midibyte *status*, midibyte *cc*, midipulse * *tick*, midibyte * *d0*, midibyte * *d1*, bool * *selected*)

Then set the rest of the parameters parameters using that event. If the status is the new value EVENT_ANY, then any event will be obtained.

Note the usage of event::is_desired_cc_or_not_cc(status, cc, *d0); Either we have a control change with the right CC or it's a different type of event.

Parameters

status	The type of event to be obtained. The special value EVENT_ANY can be provided so that no event	
	statuses are filtered.	
cc	The continuous controller value that might be desired.	
tick	A pointer return value for the tick value of the next event found.	
d0	A pointer return value for the first data value of the event.	
d1	A pointer return value for the second data value of the event.	
selected	A pointer return value for the is-selected status of the event.	
evtype	A stazed parameter for picking either all event or unselected events.	

12.67.5.154 bool seq64::sequence::get_next_event (midibyte * status, midibyte * cc)

Then set the status and control character parameters using that event.

Parameters

status	Provides a pointer to the MIDI status byte to be set, as a way to retrieve the event.
cc	The return pointer for the control value.

12.67.5.155 bool seq64::sequence::get_next_trigger (midipulse * tick_on, midipulse * tick_off, bool * selected, midipulse * tick_offset)

12.67.5.156 void seq64::sequence::quantize_events (midibyte status, midibyte cc, midipulse snap_tick, int divide, bool linked = false)

One confusing things is why the original versions of the events don't seem to be deleted.

status	Indicates the type of event to be quantized.	
cc The desired control-change to count, if the event is a control-change.		
snap_tick	Provides the maximum amount to move the events. Actually, events are moved to the previous or next snap_tick value depend on whether they are halfway to the next one or not.	
divide	A rough indicator of the amount of quantization. The only values used in the application seem to be either 1 or 2.	
linked	False by default, this parameter indicates if marked events are to be relinked, as far as we can tell.	

12.67.5.157 void seq64::sequence::push_quantize (midibyte *status*, midibyte *cc*, midipulse *snap_tick*, int *divide*, bool *linked* = false)

12.67.5.158 void seq64::sequence::transpose_notes (int steps, int scale)

If the scale value is 0, this is "no scale", which is the chromatic scale, where all 12 notes, including sharps and flats, are part of the scale.

Also, we've moved external calls to push_undo() into this function. The caller shouldn't have to do that.

Note

We noticed (ca 2016-06-10) that MIDI aftertouch events need to be transposed, but are not being transposed here. Assuming they are selectable (another question!), the test for note-on and note-off is not sufficient, and so has been replaced by a call to event::is_note_msg().

Parameters

steps	The number of steps to transpose the notes.
scale	The scale to make the notes adhere to while transposing.

12.67.5.169 midibyte seq64::sequence::musical_key() const [inline]

12.67.5.160 void seq64::sequence::musical_key(int key) [inline]

12.67.5.161 midibyte seq64::sequence::musical_scale() const [inline]

12.67.5.162 void seq64::sequence::musical_scale(int scale) [inline]

12.67.5.163 int seq64::sequence::background_sequence() const [inline]

12.67.5.164 void seq64::sequence::background_sequence(int bs) [inline]

Disabling the sequence number (setting it to SEQ64_SEQUENCE_LIMIT) is valid.

```
12.67.5.165 void seq64::sequence::show_events ( ) const
```

12.67.5.166 void seq64::sequence::copy_events (const event_list & newevents)

Compare this function to the remove_all() function. Copying the container is a lot of work, but fairly fast, even with an std::multimap as the container.

Threadsafe Note that we had to consolidate the replacement of all the events in the container in order to prevent the "Save to Sequence" button in the eventedit object from causing the application to segfault. It would segfault when the mainwand timer callback would fire, causing updates to the sequence's slot pixmap, which would then try to access deleted events. Part of the issue was that note links were dropped when copying the events, so now we call verify_and_link() to hopefully reconstitute the links.

Parameters

newevents	Provides the container of MIDI events that will completely replace the current container. Normally	
	this container is supplied by the event editor, via the eventslots class.	

```
12.67.5.167 midipulse seq64::sequence::note_off_margin() const [inline]
```

12.67.5.168 bool seq64::sequence::event_in_range (const event & e, midibyte status, midipulse tick_s, midipulse tick_f) const [inline], [private]

Makes if-clauses easier to read.

Parameters

e	Provides the event to be checked.	
status	Provides the event type that must be matched.	
tick⊷	The lower end of the range of timestamps that the event must fall within.	
_s		
tick←	The upper end of the range of timestamps that the event must fall within.	
f		

Returns

Returns true if the event matchs all of the restrictions noted.

```
12.67.5.169 void seq64::sequence::set_parent( perform * p ) [private]
```

Remember that m_parent is not at all owned by the sequence. We just don't want to do all the work necessary to make it a reference, at this time.

Parameters

ρA	pointer to the pa	arent, assigned o	only if not alread	v assigned.
----	-------------------	-------------------	--------------------	-------------

12.67.5.170 void seq64::sequence::put_event_on_bus(event & ev) [private]

This function does not bother checking if m_masterbus is a null pointer.

Parameters

ev The event to put on the buss.

Threadsafe

12.67.5.171 void seq64::sequence::set_trigger_offset (midipulse trigger_offset) [private]

If m_length is 0, then m_trigger_offset is simply set to the parameter.

Threadsafe

Parameters

trigger_offset 1	The full trigger offset to set.
------------------	---------------------------------

12.67.5.172 void seq64::sequence::adjust_trigger_offsets_to_length (midipulse newlength) [private]

Threadsafe

Might can get rid of this function?

Parameters

newlength	The new length of the adjusted trigger.
-----------	---

12.67.5.173 midipulse seq64::sequence::adjust_offset (midipulse offset) [private]

12.67.5.174 void seq64::sequence::remove(event_list::iterator i) [private]

We no longer bother checking the pointer. If it is bad, all hope is lost. If the event is a note off, and that note is currently playing, then send a note off.

Not threadsafe

Parameters

i Provides the iterator to the event to remove from the event list.

```
12.67.5.175 void seq64::sequence::remove(event & e) [private]
```

Finds the given event in m_events, and removes the first iterator matching that. If there are events that would match after that, they remain in the container. This matches seq24 behavior.

Not threadsafe

Parameters

e Provides a reference to the event to be removed.

```
12.67.5.176 void seq64::sequence::remove_all( ) [private]
```

Unsets the modified flag. (Why?) Also see the new copy_events() function.

12.67.5.177 bool seq64::sequence::channel_match (const event & e) const [inline], [private]

Parameters

e The event whose channel nybble is to be checked.

Returns

Returns true if the channel-matching feature is enable and the channels match, or true if the channel-matching feature is turned off.

12.67.6 Friends And Related Function Documentation

```
12.67.6.1 friend class perform [friend]
```

12.67.6.2 friend class triggers [friend]

12.67.7 Field Documentation

```
12.67.7.1 event list seq64::sequence::m_events_clipboard [static], [private]
```

Being static allows for copy/paste between patterns.

```
12.67.7.2 perform* seq64::sequence::m_parent [private]
```

We can use the rc_settings flag(s), but JACK could be disconnected. We could use a reference here, but, to avoid modifying the midifile class as well, we use a pointer. It is set in perform::add_sequence(). This member would also be using for passing modification status to the parent, so that the GUI code doesn't have to do it.

```
12.67.7.3 event_list seq64::sequence::m_events [private]
```

It used to be called m_list_events, but a map implementation is now available, and is the default.

```
12.67.7.4 triggers seq64::sequence::m_triggers [private]
```

```
12.67.7.5 event_list seq64::sequence::m_events_undo_hold [private]
```

Changed, of course, from std::list<event> to the sequence::Events typedef.

```
Events m_events_undo_hold;
```

```
12.67.7.6 boolseq64::sequence::m_have_undo [private]
```

```
12.67.7.7 bool seq64::sequence::m_have_redo [private]
```

Previously, unlike the perfedit, the seqedit did not provide a redo facility.

```
12.67.7.8 EventStack seq64::sequence::m_events_undo [private]
```

```
12.67.7.9 EventStack seq64::sequence::m_events_redo [private]
```

12.67.7.10 event_list::iterator seq64::sequence::m_iterator_draw [private]

```
12.67.7.11 bool seq64::sequence::m_channel_match [private]
```

If true (not yet the default), then the seqedit window will record only MIDI events that match its channel. The old behavior is preserved if this variable is set to false.

```
12.67.7.12 midibyte seq64::sequence::m_midi_channel [private]
```

However, if this value is EVENT_NULL_CHANNEL (0xFF), then this sequence is an SMF 0 track, and has no single channel.

```
12.67.7.13 midibyte seq64::sequence::m_bus [private]
```

```
12.67.7.14 bool seq64::sequence::m_song_mute [private]
```

12.67.7.15 int seq64::sequence::m_notes_on [private]

12.67.7.16 mastermidibus* seq64::sequence::m_masterbus [private]

12.67.7.17 int seq64::sequence::m_playing_notes[SEQ64_MIDI_NOTES_MAX] [private]

It is used when muting, to shut off the notes that are playing.

```
12.67.7.18 bool seq64::sequence::m_was_playing [private]
12.67.7.19 bool seq64::sequence::m_playing [private]
12.67.7.20 bool seq64::sequence::m_recording [private]
12.67.7.21 bool seq64::sequence::m_quantized_rec [private]
12.67.7.22 bool seq64::sequence::m_thru [private]
12.67.7.23 bool seq64::sequence::m_queued [private]
12.67.7.24 bool seq64::sequence::m_dirty_main [private]
Provides the main dirtiness flag.
12.67.7.25 bool seq64::sequence::m_dirty_edit [private]
12.67.7.26 bool seq64::sequence::m_dirty_perf [private]
12.67.7.27 bool seq64::sequence::m_dirty_names [private]
12.67.7.28 bool seq64::sequence::m_editing [private]
12.67.7.29 bool seq64::sequence::m_raise [private]
It allows a sequence editor window to pop up if not already raised, in seqedit::timeout().
12.67.7.30 std::string seq64::sequence::m_name [private]
12.67.7.31 midipulse seq64::sequence::m_last_tick [private]
Provides the last tick played.
12.67.7.32 midipulse seq64::sequence::m_queued_tick [private]
12.67.7.33 midipulse seq64::sequence::m_trigger_offset [private]
12.67.7.34 const int seq64::sequence::m_maxbeats [private]
```

Hardwired to c_maxbeats at present.

```
12.67.7.35 int seq64::sequence::m_ppqn [private]
```

```
12.67.7.36 int seq64::sequence::m_seq_number [private]
```

This number is set in the perform::install_sequence() function.

```
12.67.7.37 midipulse seq64::sequence::m_length [private]
```

This value should be a power of two when used as a bar unit.

```
12.67.7.38 midipulse seq64::sequence::m_snap_tick [private]
```

It starts out as the value m ppqn / 4.

```
12.67.7.39 int seq64::sequence::m_time_beats_per_measure [private]
```

Defaults to 4. Used by the sequence editor to mark things in correct time on the user-interface.

```
12.67.7.40 int seq64::sequence::m_time_beat_width [private]
```

Defaults to 4, which means the beat is a quarter note. A value of 8 would mean it is an eighth note. Used by the sequence editor to mark things in correct time on the user-interface.

```
12.67.7.41 int seq64::sequence::m_clocks_per_metronome [private]
```

This value provides the number of MIDI clocks between metronome clicks. The default value of this item is 24. It can also be read from some SMF 1 files, such as our hymne.mid example.

```
12.67.7.42 int seq64::sequence::m_32nds_per_quarter [private]
```

This value provides the number of notated 32nd notes in a MIDI quarter note (24 MIDI clocks). The usual (and default) value of this parameter is 8; some sequencers allow this to be changed.

```
12.67.7.43 long seq64::sequence::m_us_per_quarter_note [private]
```

This value can be extracted from the beats-per-minute value (mastermidibus::m_beats_per_minute), but here we set it to 0 by default, indicating that we don't want to write it. Otherwise, it can be read from a MIDI file, and saved here to be restored later.

```
12.67.7.44 int seq64::sequence::m_rec_vol [private]
```

```
12.67.7.45 int seq64::sequence::m_note_on_velocity [private]
```

Currently set to SEQ64_DEFAULT_NOTE_ON_VELOCITY. If the recording velocity (m_rec_vol) is non-zero, this value will be set to the desired recording velocity. A "stazed" feature.

```
12.67.7.46 int seq64::sequence::m_note_off_velocity [private]
```

Currently set to SEQ64_DEFAULT_NOTE_OFF_VELOCITY, and currently unmodifiable. A "stazed" feature.

```
12.67.7.47 midibyte seq64::sequence::m_musical_key [private]
```

If the value is SEQ64_KEY_OF_C, then there is no musical key to be set.

```
12.67.7.48 midibyte seq64::sequence::m_musical_scale [private]
```

If the value is the enumeration value c_scale_off, then there is no musical scale to be set.

```
12.67.7.49 int seq64::sequence::m_background_sequence [private]
```

If the value is greater than max sequence(), then there is no background sequence to be set.

```
12.67.7.50 mutex seq64::sequence::m_mutex [mutable], [private]
```

Made mutable for use in certain locked getter functions.

```
12.67.7.51 const midipulse seq64::sequence::m_note_off_margin [private]
```

Also used when the user attempts to shrink a note to zero (or less than zero) length.

12.68 seq64::trigger Class Reference

This class hold a single trigger for a sequence object.

Public Member Functions

• trigger ()

Initializes the trigger structure.

• bool operator< (const trigger &rhs)

This operator compares only the m_tick_start members.

• midipulse length () const

'Getter' function for member m_tick_end and m_tick_start.

• midipulse tick_start () const

'Getter' function for member m_tick_start

void tick_start (midipulse s)

'Setter' function for member m_tick_start

void increment tick start (midipulse s)

'Setter' function for member m_tick_start

• void decrement_tick_start (midipulse s)

'Setter' function for member m_tick_start

• midipulse tick_end () const

'Getter' function for member m_tick_end

• void tick_end (midipulse e)

'Setter' function for member m_tick_end

• void increment_tick_end (midipulse s)

'Setter' function for member m_tick_end

• void decrement_tick_end (midipulse s)

'Setter' function for member m_tick_end

• midipulse offset () const

'Getter' function for member m_offset

• void offset (midipulse o)

'Setter' function for member m_offset

· void increment offset (midipulse s)

'Setter' function for member m_offset

• void decrement_offset (midipulse s)

'Setter' function for member m_offset

• bool selected () const

'Getter' function for member m_selected

void selected (bool s)

'Setter' function for member m selected

Private Attributes

• midipulse m_tick_start

Provides the starting tick for this trigger.

• midipulse m_tick_end

Provides the ending tick for this trigger.

midipulse m_offset

Provides the offset for this trigger.

• bool m_selected

Indicates that the trigger is part of a selection.

12.68.1 Detailed Description

This class is used in playback, and is contained in the triggers class.

12.68.2 Constructor & Destructor Documentation

```
12.68.2.1 seq64::trigger::trigger() [inline]
```

12.68.3 Member Function Documentation

12.68.3.1 bool seq64::trigger::operator< (const trigger & rhs) [inline]

Parameters

```
rhs The "right-hand side" of the less-than operation.
```

Returns

Returns true if m_tick_start is less than rhs's.

```
12.68.3.2 midipulse seq64::trigger::length ( ) const [inline]
```

We've seen that some of the calculations of trigger length are wrong, being 1 tick less than the true length of the trigger in pulses. This function calculates trigger length the correct way.

```
12.68.3.3 midipulse seq64::trigger::tick_start( ) const [inline]
12.68.3.4 void seq64::trigger::tick_start ( midipulse s ) [inline]
12.68.3.5 void seq64::trigger::increment_tick_start ( midipulse s ) [inline]
12.68.3.6 void seq64::trigger::decrement_tick_start ( midipulse s ) [inline]
12.68.3.7 midipulse seq64::trigger::tick_end( ) const [inline]
12.68.3.8 void seq64::trigger::tick_end( midipulse e ) [inline]
12.68.3.9 void seq64::trigger::increment_tick_end( midipulse s ) [inline]
12.68.3.10 void seq64::trigger::decrement_tick_end ( midipulse s ) [inline]
12.68.3.11 midipulse seq64::trigger::offset() const [inline]
12.68.3.12 void seq64::trigger::offset( midipulse o ) [inline]
12.68.3.13 void seq64::trigger::increment_offset ( midipulse s ) [inline]
12.68.3.14 void seq64::trigger::decrement_offset( midipulse s ) [inline]
12.68.3.15 bool seq64::trigger::selected ( ) const [inline]
12.68.3.16 void seq64::trigger::selected (bools) [inline]
12.68.4 Field Documentation
12.68.4.1 midipulse seq64::trigger::m_tick_start [private]
12.68.4.2 midipulse seq64::trigger::m_tick_end [private]
12.68.4.3 midipulse seq64::trigger::m_offset [private]
12.68.4.4 bool seq64::trigger::m_selected [private]
```

12.69 seq64::triggers Class Reference

The triggers class is a receptable the triggers that can be used with a sequence object.

Public Member Functions

· triggers (sequence &parent)

Principal constructor.

• ∼triggers ()

A rote destructor.

• triggers & operator= (const triggers &rhs)

Principal assignment operator.

void set_ppqn (int ppqn)

'Setter' function for member m_ppqn We have to set this value after construction for best safety.

void set_length (int len)

'Setter' function for member m_length We have to set this value after construction for best safety.

· const List & triggerlist () const

'Getter' function for member m_triggers This is the const version

• List & triggerlist ()

'Getter' function for member m_triggers

· void push undo ()

Pushes the list-trigger into the trigger undo-list, then flags each item in the undo-list as unselected.

void pop_undo ()

If the trigger undo-list has any items, the list-trigger is pushed into the redo list, the top of the undo-list is coped into the list-trigger, and then pops from the undo-list.

void pop_redo ()

If the trigger redo-list has any items, the list-trigger is pushed into the undo list, the top of the redo-list is coped into the list-trigger, and then pops from the redo-list.

· void print (const std::string &seqname) const

Prints a list of the currently-held triggers.

bool play (midipulse &starttick, midipulse &endtick)

If playback-mode (song mode) is in force, that is, if using in-triggers and on/off triggers, this function handles that kind of playback.

• void add (midipulse tick, midipulse len, midipulse offset=0, bool adjustoffset=true)

Adds a trigger.

void adjust_offsets_to_length (midipulse newlen)

Adjusts trigger offsets to the length specified for all triggers, and undo triggers.

• void split (midipulse tick)

Splits the first trigger that brackets the splittick parameter.

void grow (midipulse tickfrom, midipulse tickto, midipulse length)

Grows a trigger.

· void remove (midipulse tick)

Deletes the first trigger that brackets the given tick from the trigger-list.

• bool get_state (midipulse tick)

Checks the list of triggers against the given tick.

bool select (midipulse tick)

Checks the list of triggers against the given tick.

• bool unselect ()

Unselects all triggers.

· bool intersect (midipulse position, midipulse &start, midipulse &end)

This function examines each trigger in the trigger list.

void remove_selected ()

Deletes the first selected trigger that is found.

· void copy selected ()

Copies the first selected trigger that is found.

• void paste (midipulse paste_tick=SEQ64_NO_PASTE_TRIGGER)

If there is a copied trigger, then this function grabs it from the trigger clipboard and adds it.

• bool move_selected (midipulse tick, bool adjustoffset, grow_edit_t which=GROW_MOVE)

Moves selected triggers as per the given parameters.

· midipulse get selected start ()

Gets the selected trigger's start tick.

midipulse get_selected_end ()

Gets the selected trigger's end tick.

midipulse get maximum ()

Get the ending value of the last trigger in the trigger-list.

· void move (midipulse starttick, midipulse distance, bool direction)

Moves triggers in the trigger-list.

· void copy (midipulse starttick, midipulse distance)

Not sure what these diagrams are for yet.

• void clear ()

Clears the whole list of triggers.

bool next (midipulse *tick_on, midipulse *tick_off, bool *selected, midipulse *tick_offset)

Get the next trigger in the trigger list, and set the parameters based on that trigger.

trigger next_trigger ()

Get the next trigger in the trigger list.

void reset draw trigger marker ()

Sets the draw-trigger iterator to the beginning of the trigger list.

- void set trigger paste tick (midipulse tick)
- midipulse get_trigger_paste_tick () const

Private Types

typedef std::list< trigger > List

Exposes the triggers type, currently needed for midi_container only.

typedef std::stack< List > Stack

Provides a stack for use with the undo/redo features of the trigger support.

Private Member Functions

· midipulse adjust_offset (midipulse offset)

Adjusts the given offset by mod'ing it with m_length and adding m_length if needed, and returning the result.

void split (trigger &trig, midipulse splittick)

Splits the trigger given by the parameter into two triggers.

Private Attributes

· sequence & m_parent

Holds a reference to the parent sequence object that owns this trigger object.

· List m_triggers

This list holds the current pattern/triggers events.

• trigger m_clipboard

This item holds a single copied trigger, to be pasted later.

· Stack m undo stack

Handles the undo list for a series of operations on triggers.

Stack m_redo_stack

Handles the redo list for a series of operations on triggers.

• List::iterator m_iterator_play_trigger

An iterator for cycling through the triggers during playback.

· List::iterator m_iterator_draw_trigger

An iterator for cycling through the triggers during drawing.

bool m_trigger_copied

Set to true if there is an active trigger in the trigger clipboard.

midipulse m_paste_tick

The tick point for pasting.

• int m_ppqn

Holds the value of the PPQN from the parent sequence, for easy access.

· int m_length

Holds the value of the length from the parent sequence, for easy access.

Friends

- · class midi container
- · class midifile
- · class sequence
- class Seq24PerfInput
- class FruityPerfInput

12.69.1 Member Typedef Documentation

```
12.69.1.1 typedef std::list<trigger> seq64::triggers::List [private]
```

12.69.1.2 typedef std::stack<List> seq64::triggers::Stack [private]

12.69.2 Member Enumeration Documentation

```
12.69.2.1 enum seq64::triggers::grow_edit_t [private]
```

Enumerator

GROW_START Grow the start of the trigger.

GROW_END Grow the end of the trigger.

GROW_MOVE Move the entire trigger block.

12.69.3 Constructor & Destructor Documentation

12.69.3.1 seq64::triggers::triggers (sequence & parent)

Parameters

parent The triggers object often needs to tell its parent sequence object what to do (such as stop playing).

```
12.69.3.2 seq64::triggers::~triggers ( )
```

12.69.4 Member Function Documentation

```
12.69.4.1 triggers & seq64::triggers::operator= ( const triggers & rhs )
```

Follows the stock rules for such an operator, but does a little more then just assign member values.

FIXED, BEWARE: Currently, it does not assign them all, so we should create a partial_copy() function to do this work, and use it where it is needed.

Parameters

```
rhs Provides the "right-hand side" of the assignment operation.
```

Returns

Returns a reference to self, for use in concatenated assignment operations.

```
12.69.4.2 void seq64::triggers::set_ppqn(int ppqn) [inline]
12.69.4.3 void seq64::triggers::set_length(int len) [inline]
```

Also, there a chance that the length of the parent might change from time to time. Currently, only the sequence constructor and midifile call this function.

```
12.69.4.4 const List& seq64::triggers::triggerlist() const [inline]

12.69.4.5 List& seq64::triggers::triggerlist() [inline]

12.69.4.6 void seq64::triggers::push_undo()

12.69.4.7 void seq64::triggers::pop_undo()

12.69.4.8 void seq64::triggers::pop_redo()

12.69.4.9 void seq64::triggers::print( const std::string & seqname) const
```

Parameters

```
seqname A tag name to accompany the print-out, for the human to read.
```

12.69.4.10 bool seq64::triggers::play (midipulse & start_tick, midipulse & end_tick)

This is a new function for sequence::play() to call.

The for-loop goes through all the triggers, determining if there is are trigger start/end values before the *end_tick*. If so, then the trigger state is set to true (start only within the tick range) or false (end is within the tick range), and the trigger tick is set to start or end. The first start or end trigger that is past the end tick cause the search to end.

If the trigger state has changed, then the start/end ticks are passed back to the sequence, and the trigger offset is adjusted.

Parameters

start_tick	Provides the starting tick value, and returns the modified value as a side-effect.
end_tick	Provides the ending tick value, and returns the modified value as a side-effect.

Returns

Returns true if we're through playing the frame (trigger turning off), and the caller should stop the playback.

12.69.4.11 void seq64::triggers::add (midipulse tick, midipulse len, midipulse offset = 0, bool fixoffset = true)

What is this?

Parameters

tick	Provides the tick (pulse) time at which the trigger goes on.
len	Provides the length of the trigger. This value is actually calculated from the "on" value minus the "off" value read from the MIDI file.
offset	This value specifies the offset of the trigger. It is a feature of the c_triggers_new that c_triggers doesn't have. It is the third value in the trigger specification of the Sequencer64 MIDI file.
fixoffset	If true, the offset parameter is modified by adjust_offset() first. We think that basically makes sure it is positive.

12.69.4.12 void seq64::triggers::adjust_offsets_to_length (midipulse newlength)

Parameters

newlength	Provides the length to which to adjust the offsets.

COMMON CODE?

12.69.4.13 void seq64::triggers::split (midipulse splittick)

This is the first trigger where splittick is greater than L and less than R.

Parameters

	splittick	Provides the tick that must be bracketed for the split to be made.	
--	-----------	--	--

12.69.4.14 void seq64::triggers::grow (midipulse tickfrom, midipulse tickto, midipulse len)

This function looks for the first trigger where the tickfrom parameter is between the trigger's tick-start and tick-end values. If found then the trigger's start is moved back to tickto, if necessary, or the trigger's end is moved to tickto plus the length parameter, if necessary.

Then this new trigger is added, and the function breaks from the search loop.

Parameters

tickfrom	The desired from-value back which to expand the trigger, if necessary.
tickto	The desired to-value towards which to expand the trigger, if necessary.
len	The additional length to append to tickto for the check.

12.69.4.15 void seq64::triggers::remove (midipulse tick)

Parameters

tick	Provides the tick to be examined.
------	-----------------------------------

12.69.4.16 bool seq64::triggers::get_state (midipulse tick)

If any trigger is found to bracket that tick, then true is returned.

Parameters

tick	Provides the tick of interest.

Returns

Returns true if a trigger is found that brackets the given tick.

12.69.4.17 bool seq64::triggers::select (midipulse tick)

If any trigger is found to bracket that tick, then true is returned, and the trigger is marked as selected.

Parameters

tick	Provides the tick of interest.
------	--------------------------------

Returns

Returns true if a trigger is found that brackets the given tick.

12.69.4.18 bool seq64::triggers::unselect ()

Returns

Always returns false.

12.69.4.19 bool seq64::triggers::intersect (midipulse position, midipulse & start, midipulse & ender)

If the given position is between the current trigger's tick-start and tick-end values, the these values are copied to the start and end parameters, respectively, and then we exit.

Parameters

position	The position to examine.
start	The destination for the starting tick (m_tick_start) of the matching trigger.
ender	The destination for the ending tick (m_tick_end) of the matching trigger.

Returns

Returns true if a trigger was found whose start/end ticks contained the position. Otherwise, false is returned, and the start and end return parameters should not be used.

```
12.69.4.20 void seq64::triggers::remove_selected ( )
```

12.69.4.21 void seq64::triggers::copy_selected ()

12.69.4.22 void seq64::triggers::paste (midipulse paste_tick = SEQ64_NO_PASTE_TRIGGER)

It pastes at the copy end. or at the paste-tick, if supplied.

Parameters

paste_tick	Provides the optional tick at which to paste the trigger. If not set to
	SEQ64_NO_PASTE_TRIGGER, this value is used to adjust the paste offset.

12.69.4.23 bool seq64::triggers::move_selected (midipulse tick, bool fixoffset, grow_edit_t which = GROW_MOVE)

1][maxtick

```
The \a which parameter has three possible values:

-# If we are moving the 0, use first as offset.

-# If we are moving the 1, use the last as the offset.
```

-# If we are moving both (2), use first as offset.

mintick][0

Parameters

tick	The tick at which the trigger starts.
fixoffset	Set to true if the offset is to be adjusted.
which	Selects which movement will be done, as discussed above. See the values of the
	trigger::grow_edit_t type.

Returns

Returns true if there was room to move. Otherwise, false is returned. We need this feature to support keystoke movement of a selected trigger in the perfroll window, and keep it from continually incrementing when there can be no more movement. This causes moving the other direction to be delayed while the accumulating movement counter is used up. However, right now we can't rely on this result, and ignore it. There may be no way around this minor issue.

12.69.4.24 midipulse seq64::triggers::get_selected_start()

We guess this ends up selecting only one trigger, otherwise only the last selected one would effectively set the result.

Returns

Returns the tick_start() value of the last-selected trigger. If no triggers are selected, then midipulse(-1) is returned.

12.69.4.25 midipulse seq64::triggers::get_selected_end()

Returns

Returns the tick_end() value of the last-selected trigger. If no triggers are selected, then midipulse(-1) is returned.

12.69.4.26 midipulse seq64::triggers::get_maximum ()

Returns

Returns the tick-end for the last trigger, if available. Otherwise, 0 is returned.

12.69.4.27 void seq64::triggers::move (midipulse starttick, midipulse distance, bool direction)

There's no way to optimize this by saving tick values, as they are potentially modified at each step.

Parameters

	starttick	The current location of the triggers.
	distance	The distance away from the current location to which to move the triggers.
ĺ	direction	If true, the triggers are moved forward. If false, the triggers are moved backward.

12.69.4.28 void seq64::triggers::copy (midipulse starttick, midipulse distance)

```
[ ][ ]
. . .
... a
. . .
5
  7 play
      offset
8 10 play
] [ ] [] orig
[
[
      [ ] [ ][] split on the R marker, shift first [ ] [ ]
      delete middle
        ][][][
                 move ticks
         ][][] [] split on L
            [ ] [] increase all after L
|...|...|...|...
0123456789abcdef0123456789abcdef
][ ][ ][ ][ ]
[ ][
      ][][][][][][
                     ] [ ][ ]
       4 0 7 4 2 0
4 0 1 4 6 0
 4
                        6 2
2 6 inverse offset
0
           ] [
                      ] [
    ] [ ][ ]
 ] [
 С
                         2 6 inverse offset
                       ] [
 ][][][][][][][][
                      ] [ ] [ ]
 gfca8
          ghkmn
                      inverse offset
       С
0123456789abcdefghijklmonpq
ponmlkjihgfedcba9876543210
Ofedcba9876543210fedcba9876543210fedcba9876543210fedcba9876543210
```

Copies triggers to a point distant from a given tick.

Parameters

starttick	The current location of the triggers.
distance	The distance away from the current location to which to copy the triggers.

```
12.69.4.29 void seq64::triggers::clear() [inline]
```

12.69.4.30 bool seq64::triggers::next (midipulse * tick_on, midipulse * tick_off, bool * selected, midipulse * offset)

Todo It would be a bit simpler to simply return a trigger object, wouldn't it?

Parameters

tick_on	Return value for the retrieval of the starting tick for the trigger.
tick_off	Return value for the retrieval of the ending tick for the trigger.
selected	Return value for the retrieval of the is-selected flag for the trigger.
offset	Return value for the retrieval of the offset for the trigger.

Returns

Returns true if a trigger was found. If false, the caller cannot rely on the values returned through the return parameters.

Side-effect(s) The value of the m_iterator_draw_trigger member will be altered by this call, unless pointing to the end of the triggerlist, or if there are no triggers.

```
12.69.4.31 trigger seq64::triggers::next_trigger()
```

Returns

Returns the next trigger. If there is none, a default trigger object is returned.

```
12.69.4.32 void seq64::triggers::reset_draw_trigger_marker( ) [inline]

12.69.4.33 void seq64::triggers::set_trigger_paste_tick( midipulse tick ) [inline]

12.69.4.34 midipulse seq64::triggers::get_trigger_paste_tick( ) const [inline]

12.69.4.35 midipulse seq64::triggers::adjust_offset( midipulse offset ) [private]
```

Parameters

offset	Provides the offset, mod'ed against m_length, used to adjust the offset.
--------	--

Returns

Returns the new offset. However, if m_length is 0, no change is made, and the original offset is returned.

```
12.69.4.36 void seq64::triggers::split (trigger & trig, midipulse splittick) [private]
```

The original trigger ends 1 tick before the splittick parameter, and the new trigger starts at splittick and ends where the original trigger ended.

Parameters

trig	Provides the original trigger, and also holds the changes made to that trigger as it is shortened, as a side-effect.
splittick	The position just after where the original trigger will be truncated, and the new trigger begins.

12.69.5 Friends And Related Function Documentation 12.69.5.1 friend class midi_container [friend] **12.69.5.2 friend class midifile** [friend] **12.69.5.3 friend class sequence** [friend] **12.69.5.4** friend class Seq24PerfInput [friend] 12.69.5.5 friend class FruityPerfInput [friend] 12.69.6 Field Documentation 12.69.6.1 sequence& seq64::triggers::m_parent [private] **12.69.6.2 List seq64::triggers::m_triggers** [private] **12.69.6.3 trigger seq64::triggers::m_clipboard** [private] 12.69.6.4 Stack seq64::triggers::m_undo_stack [private] **12.69.6.5 Stack seq64::triggers::m_redo_stack** [private] **12.69.6.6 List::iterator seq64::triggers::m_iterator_play_trigger** [private] **12.69.6.7 List::iterator seq64::triggers::m_iterator_draw_trigger** [private] **12.69.6.8** bool seq64::triggers::m_trigger_copied [private] **12.69.6.9** midipulse seq64::triggers::m_paste_tick [private]

Set to -1 if not in force. This is a new feature from stazed's Seq32 project.

```
12.69.6.10 int seq64::triggers::m_ppqn [private]
```

This should not change, but we have to set it after construction, and so we provide a setter for it, set_ppqn(), called by the sequence constructor.

```
12.69.6.11 int seq64::triggers::m_length [private]
```

This might change, we're not yet sure.

12.70 seg64::user instrument Class Reference

Provides data about the MIDI instruments, readable from the "user" configuration file.

Public Member Functions

user instrument (const std::string &name="")

Default constructor.

user_instrument (const user_instrument &rhs)

Copy constructor.

user_instrument & operator= (const user_instrument &rhs)

Principal assignment operator.

• bool is_valid () const

'Getter' function for member m_is_valid

· void set_defaults ()

Sets the default values.

• const std::string & name () const

'Getter' function for member m_instrument_def.instrument (name of instrument)

• int controller_count () const

'Getter' function for member m_controller_count This function returns the number of active controllers.

• int controller_max () const

'Getter' function for member MIDI_CONTROLLER_MAX This function returns the maximum number of controllers, active or inactive.

const std::string & controller_name (int c) const

 ${\it 'Getter' function for member m_instrument_def.controllers[c]}$

• bool controller_active (int c) const

'Getter' function for member m_instrument_def.controllers_active[c]

• void set_controller (int c, const std::string &cname, bool isactive)

'Setter' function for member m_instrument_def.controllers[c] and .controllers_active[c] Only sets the controller values if the object is already valid.

Private Member Functions

void set_name (const std::string &instname)

'Setter' function for member m_instrument_def.instrument If the name parameter is not empty, the validity flag is set to true, otherwise it is set to false.

void copy_definitions (const user_instrument &rhs)

Copies the array members from one instance of user_instrument to this one.

Private Attributes

• bool m_is_valid

Provides a validity flag, useful in returning a reference to a bogus object for internal error-check.

• int m_controller_count

Provides the actual number of non-default controllers actually set.

· user_instrument_t m_instrument_def

The instance of the structure that this class wraps.

12.70.1 Detailed Description

Will later make the size adjustable, if it makes sense to do so.

12.70.2 Constructor & Destructor Documentation

```
12.70.2.1 seq64::user_instrument::user_instrument ( const std::string & name = " " )
```

Fills in the defaults for the instrument definition, sets its name, and provides some light validation.

Parameters

name The name of the instrument, valid only if it is not empty.

12.70.2.2 seq64::user_instrument::user_instrument (const user_instrument & rhs)

Parameters

```
rhs The sources of the data for the copy.
```

12.70.3 Member Function Documentation

12.70.3.1 user_instrument & seq64::user_instrument::operator= (const user_instrument & rhs)

Parameters

rhs The sources of the data for the assignment.

Returns

Returns a reference to this object.

```
12.70.3.2 bool seq64::user_instrument::is_valid( ) const [inline]
```

12.70.3.3 void seq64::user_instrument::set_defaults()

Also invalidates the object.

```
12.70.3.4 const std::string& seq64::user_instrument::name( ) const [inline]
```

12.70.3.5 int seq64::user_instrument::controller_count() const [inline]

12.70.3.6 int seq64::user_instrument::controller_max () const [inline]

Remember that the controller numbers for each MIDI instrument range from 0 to 127 (MIDI_CONTROLLER_MAX-1).

12.70.3.7 const std::string & seq64::user_instrument::controller_name (int c) const

Parameters

c The index of the desired controller.

Returns

The name of the desired controller has is returned. If the index c is out of range, or the object is not valid, then a reference to an internal, empty string is returned.

12.70.3.8 bool seq64::user_instrument::controller_active (int c) const

Parameters

c The index of the desired controller.

Returns

The status of the desired controller has is returned. If the index c is out of range, or the object is not valid, then false is returned.

12.70.3.9 void seq64::user_instrument::set_controller (int c, const std::string & cname, bool isactive)

Parameters

С	The index of the desired controller.
cname	The name of the controller to be set as the controller name.
isactive	A flag that indicates if the desired controller is active.

12.70.3.10 void seq64::user_instrument::set_name (const std::string & instname) [private]

Too tricky?

Parameters

instname	The name of the instrument, valid only if it is not empty.
----------	--

12.70.3.11 void seq64::user_instrument::copy_definitions (const user_instrument & rhs) [private]

Does not include the validity flag.

Parameters

rhs The sources of the data for the partial copy.

12.70.4 Field Documentation

12.70.4.1 bool seq64::user_instrument::m_is_valid [private]

Callers should check this flag via the is_valid() accessor before using this object. This flag is set to true when any valid member assignment occurs via a public setter call. However, setting an empty name for the instrument member will render the object invalid.

12.70.4.2 int seq64::user_instrument::m_controller_count [private]

Often, the "user" configuration file has only a few out of the 128 assigned explicitly.

12.70.4.3 user_instrument_t seq64::user_instrument::m_instrument_def [private]

12.71 seq64::user_instrument_t Struct Reference

This structure corresponds to [user-instrument-N] definitions in the \sim /.seq24usr or \sim /.config/sequencer64/susr file.

Data Fields

· std::string instrument

Provides the name of the "instrument" being supported.

std::string controllers [SEQ64_MIDI_CONTROLLER_MAX]

Provides a list of up to 128 controllers (e.g.

· bool controllers_active [SEQ64_MIDI_CONTROLLER_MAX]

Provides a flag that indicates if each of up to 128 controller is active and supported.

12.71.1 Field Documentation

12.71.1.1 std::string seq64::user_instrument_t::instrument

Do not confuse "instrument" with "program" here. An "instrument" is most likely a hardware MIDI sound-box (though it could be a software synthesizer as well.

12.71.1.2 std::string seq64::user_instrument_t::controllers[SEQ64_MIDI_CONTROLLER_MAX]

"Modulation"). If a controller isn't present, or if General MIDI is in force, this name might be empty.

12.71.1.3 bool seq64::user_instrument_t::controllers_active[SEQ64_MIDI_CONTROLLER_MAX]

If false, it might be an unsupported controller or a General MIDI device.

12.72 seq64::user_midi_bus Class Reference

Provides data about the MIDI busses, readable from the "user" configuration file.

Public Member Functions

• user_midi_bus (const std::string &name="")

Default constructor.

• user_midi_bus (const user_midi_bus &rhs)

Copy constructor.

• user_midi_bus & operator= (const user_midi_bus &rhs)

Principal assignment operator.

• bool is_valid () const

'Getter' function for member m_is_valid

void set_defaults ()

Sets the default values.

• const std::string & name () const

'Getter' function for member m_midi_bus_def.alias (name of alias)

• int channel_count () const

'Getter' function for member m_channel_count

• int channel_max () const

'Getter' function for member SEQ64_MIDI_BUS_CHANNEL_MAX

• int instrument (int channel) const

'Getter' function for member m_midi_bus_def.instrument[channel]

void set_instrument (int channel, int instrum)

'Getter' function for member m_midi_bus_def.instrument[channel]

Private Member Functions

void set_name (const std::string &name)

'Setter' function for member m_midi_bus_def.alias (name of alias) Also sets the validity flag according to the emptiness of the name parameter.

void copy_definitions (const user_midi_bus &rhs)

Copies the member fields from one instance of user_midi_bus to this one.

Private Attributes

• bool m_is_valid

Provides a validity flag, useful in returning a reference to a bogus object for internal error-check.

• int m_channel_count

Provides the actual number of non-default buss channels actually set.

• user_midi_bus_t m_midi_bus_def

The instance of the structure that this class wraps.

12.72.1 Detailed Description

Will later make the size adjustable, if it makes sense to do so.

12.72.2 Constructor & Destructor Documentation

```
12.72.2.1 seq64::user_midi_bus::user_midi_bus ( const std::string & name = " " )
```

Parameters

name	The name of the buss, valid only if it is not empty.
------	--

12.72.2.2 seq64::user_midi_bus::user_midi_bus (const user_midi_bus & rhs)

Parameters

rhs The sources of the data for the copy.

12.72.3 Member Function Documentation

12.72.3.1 user_midi_bus & seq64::user_midi_bus::operator= (const user_midi_bus & rhs)

Parameters

```
rhs The sources of the data for the assignment.
```

Returns

Returns a reference to this object.

```
12.72.3.2 bool seq64::user_midi_bus::is_valid( ) const [inline]
```

12.72.3.3 void seq64::user_midi_bus::set_defaults ()

Also invalidates the object. All 16 of the channels are set to SEQ64_GM_INSTRUMENT_FLAG (-1).

```
12.72.3.4 const std::string& seq64::user_midi_bus::name( ) const [inline]
```

12.72.3.5 int seq64::user_midi_bus::channel_count() const [inline]

Returns

This function returns the number of channels. Basically this value is always the same as that returned by channel_max(), but this pair of functions is consistent with the count functions in the user_instrument class.

```
12.72.3.6 int seq64::user_midi_bus::channel_max() const [inline]
```

Returns

Returns the maximum number of MIDI buss channels. Remember that the instrument channels for each MIDI buss range from 0 to 15 (MIDI_BUS_CHANNEL_MAX-1).

12.72.3.7 int seq64::user_midi_bus::instrument (int channel) const

Parameters

channel Provides the desired buss channel number
--

Returns

The instrument number of the desired buss channel is returned. If the channel number is out of range, or the object is not valid, then SEQ64_GM_INSTRUMENT_FLAG (-1) is returned.

12.72.3.8 void seq64::user_midi_bus::set_instrument (int channel, int instrum)

Does not alter the validity flag, just checks it.

Parameters

channel	Provides the desired buss channel number.
instrum	Provides the instrument number to set that channel to.

12.72.3.9 void seq64::user_midi_bus::set_name(const std::string & name) [inline], [private]

12.72.3.10 void seq64::user_midi_bus::copy_definitions(const user_midi_bus & rhs) [private]

Does not include the validity flag.

12.72.4 Field Documentation

12.72.4.1 bool seq64::user_midi_bus::m_is_valid [private]

Callers should check this flag via the is_valid() accessor before using this object. This flag is set to true when any valid member assignment occurs via a public setter call.

12.72.4.2 int seq64::user_midi_bus::m_channel_count [private]

Often, the "user" configuration file has only a few out of the 16 assigned explicitly.

12.72.4.3 user_midi_bus_t seq64::user_midi_bus::m_midi_bus_def [private]

12.73 seq64::user_midi_bus_t Struct Reference

This structure corresponds to [user-midi-bus-0] definitions in the \sim /.seq24usr ("user") file (\sim /.config/sequencer64/sequencer64.usr in the latest version of the application).

Data Fields

· std::string alias

Provides the user's desired name for the MIDI bus.

int instrument [SEQ64_MIDI_BUS_CHANNEL_MAX]

Provides an implicit list of MIDI channels from 0 to 15 (1 to 16) and the "instrument" number assigned to each channel.

12.73.1 Field Documentation

12.73.1.1 std::string seq64::user_midi_bus_t::alias

For example, "2x2 A" for some kind of MIDI card or USB MIDI cable. If manual-alsa-ports is enabled, this could be something like "[0] seq24 0", and that is what should be shown in that case.

12.73.1.2 int seq64::user_midi_bus_t::instrument[SEQ64_MIDI_BUS_CHANNEL_MAX]

Note that the "instrument" is not a MIDI program number. Instead, it is the number associated with a "user-instrument" section in the "user" configuration file.

12.74 seq64::user_settings Class Reference

Holds the current values of sequence settings and settings that can modify the number of sequences and the configuration of the user-interface.

Public Member Functions

user_settings ()

Default constructor.

· user settings (const user settings &rhs)

Copy constructor.

user_settings & operator= (const user_settings &rhs)

Principal assignment operator.

· void set defaults ()

Sets the default values.

• void normalize ()

Calculate the derived values from the already-set values.

bool add_bus (const std::string &alias)

Adds a user buss to the container, but only does so if the name parameter is not empty.

bool add instrument (const std::string &instname)

Adds a user instrument to the container, but only does so if the name parameter is not empty.

const user midi bus & bus (int index)

'Getter' function for member Unlike the non-const version this function is public.

const user_instrument & instrument (int index)

'Getter' function for member Unlike the non-const version this function is public.

• int bus_count () const

'Getter' function for member m_midi_buses.size()

void set bus instrument (int index, int channel, int instrum)

'Getter' function for member m_midi_buses[index].instrument[channel] Currently this function is used, in the userfile ::parse() function.

• int bus_instrument (int buss, int channel)

'Getter' function for member m_midi_buses[buss].instrument[channel]

• const std::string & bus_name (int buss)

'Getter' function for member m_midi_buses[buss].name

· int instrument count () const

'Getter' function for member m_instruments.size()

· void set instrument controllers (int index, int cc, const std::string &ccname, bool isactive)

'Setter' function for member m_midi_instrument_defs[index].controllers, controllers_active

const std::string & instrument_name (int instrum)

'Getter' function for member m_instruments[instrument].instrument (name of instrument)

• const std::string & instrument_name (int buss, int channel)

Gets the correct instrument number from the buss and channel, and then looks up the name of the instrument.

bool instrument_controller_active (int instrum, int cc)

'Getter' function for member m_instruments[instrument].controllers_active[controller]

bool controller_active (int buss, int channel, int cc)

A convenience function so that the caller doesn't have to get the instrument number from the bus_instrument() member function.

const std::string & instrument_controller_name (int instrum, int cc)

'Getter' function for member m_instruments[instrument].controllers_active[controller]

• const std::string & controller name (int buss, int channel, int cc)

'Getter' function for member m_instruments[instrument].controllers_active[controller] A convenience function so that the caller doesn't have to get the instrument number from the bus_instrument() member function.

int grid_style () const

'Getter' function for member m_grid_style Checks for normal style.

· bool grid is normal () const

'Getter' function for member m_grid_style Checks for normal style.

· bool grid_is_white () const

'Getter' function for member m_grid_style Checks for the white style.

bool grid_is_black () const

'Getter' function for member m_grid_style Checks for the black style.

• int grid brackets () const

'Getter' function for member m_grid_brackets

• int mainwnd_rows () const

'Getter' function for member m_mainwnd_rows

int mainwnd_cols () const

'Getter' function for member m_mainwnd_cols

• int seqs_in_set () const

'Getter' function for member m_seqs_in_set, dependent member

int gmute_tracks () const

'Getter' function for member m_gmute_tracks, dependent member

int max_sets () const

'Getter' function for member m max sets

int max_sequence () const

'Getter' function for member m_max_sequence, dependent member

int text_x () const

'Getter' function for member m_text_x, not user modifiable, not saved

int text_y () const

'Getter' function for member m_text_y, not user modifiable, not saved

• int seqchars x () const

'Getter' function for member m_seqchars_x, not user modifiable, not saved

int seqchars_y () const

'Getter' function for member m_seqchars_y, not user modifiable, not saved

• int seqarea_x () const

'Getter' function for member m_seqarea_x, not user modifiable, not saved

int seqarea_y () const

'Getter' function for member m_seqarea_y, not user modifiable, not saved

• int seqarea_seq_x () const

'Getter' function for member m_seqarea_seq_x, not user modifiable, not saved

• int seqarea_seq_y () const

'Getter' function for member m_seqarea_seq_y, not user modifiable, not saved

int mainwid_border () const

'Getter' function for member m_mainwid_border

• int mainwid_spacing () const

'Getter' function for member m_mainwid_spacing

int mainwid_x () const

'Getter' function for member m_mainwid_x, dependent member

int mainwid_y () const

'Getter' function for member m_mainwid_y, dependent member

• int control_height () const

'Getter' function for member m_control_height

• int zoom () const

'Getter' function for member m_current_zoom

• void zoom (int value)

'Setter' function for member m_current_zoom This value is not modified unless the value parameter is between 1 and 512, inclusive.

· bool global_seq_feature () const

'Getter' function for member m_global_seq_feature_save

void global_seq_feature (bool flag)

'Setter' function for member m_global_seq_feature_save

• int seqedit_scale () const

'Getter' function for member m segedit scale

· void segedit scale (int scale)

'Setter' function for member m_seqedit_scale

• int seqedit_key () const

'Getter' function for member m_seqedit_key

void seqedit_key (int key)

'Setter' function for member m_seqedit_key

• int seqedit_bgsequence () const

'Getter' function for member m_seqedit_bgsequence

• void seqedit_bgsequence (int seqnum)

'Setter' function for member m_seqedit_bgsequence Note that SEQ64_IS_LEGAL_SEQUENCE() allows the SE← Q64_SEQUENCE_LIMIT (0x800 = 2048) value, to turn off the use of a background sequence.

bool use_new_font () const

'Getter' function for member m_use_new_font

bool allow_two_perfedits () const

'Getter' function for member m_allow_two_perfedits

• int perf_h_page_increment () const

'Getter' function for member m_h_perf_page_increment

• int perf_v_page_increment () const

'Getter' function for member m_v_perf_page_increment

• int progress_bar_colored () const

'Getter' function for member m_progress_bar_colored

· bool progress_bar_thick () const

'Getter' function for member m_progress_bar_thick

· bool inverse colors () const

Accessor m_inverse_colors

int window_redraw_rate () const

'Getter' function for member m window redraw rate ms

· bool save_user_config () const

'Getter' function for member m_save_user_config

• void save_user_config (bool flag)

'Setter' function for member m_save_user_config

• int midi_ppqn () const

'Getter' function for member m_midi_ppqn

• int midi_beats_per_bar () const

'Getter' function for member m_midi_beats_per_measure

int midi_beats_per_minute () const

 ${\it 'Getter' function for member m_midi_beats_per_minute}$

• int midi_beat_width () const

'Getter' function for member m_midi_beat_width

char midi_buss_override () const

 ${\it 'Getter' function for member m_midi_buss_override}$

• int min_zoom () const

'Getter' function for member mc_min_zoom

• int max_zoom () const

'Getter' function for member mc_max_zoom

• int baseline ppqn () const

'Getter' function for member mc_baseline_ppqn

• void use_new_font (bool flag)

'Setter' function for member m_use_new_font

void allow_two_perfedits (bool flag)

Sets the value of allowing two perfedits to be created and shown to the user.

void perf h page increment (int inc)

Sets the horizontal page increment size for the horizontal scrollbar of a perfedit window.

void perf_v_page_increment (int inc)

Sets the vertical page increment size for the vertical scrollbar of a perfedit window.

void progress_bar_colored (int palcode)

'Setter' function for member m progress bar colored

void progress_bar_thick (bool flag)

'Setter' function for member m_progress_bar_thick

void inverse_colors (bool flag)

'Setter' function for member m_inverse_colors

void window_redraw_rate (int ms)

'Setter' function for member m_window_redraw_rate_ms

void midi ppqn (int ppqn)

'Setter' function for member m_midi_ppqn This value can be set from 96 to 19200 (this upper limit will be determined by what Sequencer64 can actually handle).

• void midi_buss_override (char buss)

'Setter' function for member m_midi_buss_override This value can be set from 0 to 31.

Protected Member Functions

· void grid brackets (int thickness)

'Getter' function for member m_grid_brackets

• void grid_style (int gridstyle)

'Setter' function for member m_grid_style

void mainwnd_rows (int value)

'Setter' function for member m_mainwnd_rows This value is not modified unless the value parameter is between 4 and 8, inclusive.

· void mainwnd cols (int value)

'Setter' function for member m_mainwnd_cols This value is not modified unless the value parameter is between 8 and 10. inclusive.

· void max sets (int value)

'Setter' function for member m_max_sets This value is not modified unless the value parameter is between 32 and 64. inclusive.

void text_x (int value)

'Setter' function for member m_text_x This value is not modified unless the value parameter is between 6 and 6, inclusive.

void text_y (int value)

'Setter' function for member m_text_y This value is not modified unless the value parameter is between 12 and 12, inclusive.

void seqchars_x (int value)

'Setter' function for member m_seqchars_x This affects the size or crampiness of a pattern slot, and for now we will hardwire it to 15.

void seqchars_y (int value)

'Setter' function for member m_seqchars_y This affects the size or crampiness of a pattern slot, and for now we will hardwire it to 5.

void seqarea_x (int value)

'Setter' function for member m_segarea_x

void seqarea_y (int value)

'Setter' function for member m_seqarea_y

void seqarea_seq_x (int value)

'Setter' function for member m segarea seg x

void seqarea_seq_y (int value)

'Setter' function for member m_seqarea_seq_y

void mainwid_border (int value)

'Setter' function for member m_mainwid_border This value is not modified unless the value parameter is between 0 and 3, inclusive.

void mainwid spacing (int value)

'Setter' function for member m_mainwid_spacing This value is not modified unless the value parameter is between 2 and 6, inclusive.

void control_height (int value)

'Setter' function for member m_control_height This value is not modified unless the value parameter is between 0 and 4, inclusive.

• void dump_summary ()

Provides a debug dump of basic information to help debug a surprisingly intractable problem with all busses having the name and values of the last buss in the configuration.

• void midi_beats_per_bar (int beatsperbar)

'Setter' function for member m_midi_beats_per_measure This value can be set from 1 to 16.

void midi_beats_per_minute (int beatsperminute)

'Setter' function for member m midi beats minute This value can be set from 20 to 500.

void midi_beat_width (int beatwidth)

'Setter' function for member m_midi_beatwidth This value can be set to any power of 2 in the range from 1 to 16.

Private Types

• typedef std::vector< user_midi_bus > Busses

[user-midi-bus-definitions]

- typedef std::vector< user_midi_bus >::iterator BussIterator
- typedef std::vector< user_midi_bus >::const_iterator BussConstIterator
- typedef std::vector< user_instrument > Instruments

[user-instrument-definitions]

- typedef std::vector< user_instrument >::iterator InstrumentIterator
- typedef std::vector< user_instrument >::const_iterator InstrumentConstIterator

Private Member Functions

user_midi_bus & private_bus (int buss)

'Getter' function for member m_midi_buses[index] (internal function) If the index is out of range, then an invalid object is returned.

user_instrument & private_instrument (int instrum)

'Getter' function for member m_instruments[index] If the index is out of range, then a invalid object is returned.

Private Attributes

• Busses m_midi_buses

Provides data about the MIDI busses, readable from the "user" configuration file.

· Instruments m instruments

Provides data about the MIDI instruments, readable from the "user" configuration file.

• mainwid_grid_style_t m_grid_style

[user-interface-settings]

· int m grid brackets

Specify drawing brackets (like the old Seq24) or a solid box.

· int m mainwnd rows

Number of rows in the Patterns Panel.

· int m mainwnd cols

Number of columns in the Patterns Panel.

int m_max_sets

Maximum number of screen sets that can be supported.

· int m mainwid border

These control sizes.

- · int m mainwid spacing
- · int m control height

This constants seems to be created for a future purpose, perhaps to reserve space for a new bar on the mainwid pane.

int m_current_zoom

Provides the initial zoom value, in units of ticks per pixel.

bool m_global_seq_feature_save

If true, this value provide a bit of backward-compatibility with the global key/scale/background-sequence persistence feature.

· int m_seqedit_scale

Replaces sequence is loaded into the sequence editor.

· int m segedit key

Replaces sequent::m_initial_key as the repository for the key to apply when a sequence is loaded into the sequence editor.

• int m_seqedit_bgsequence

Replaces sequedit::m_initial_sequence as the repository for the background sequence to apply when a sequence is loaded into the sequence editor.

• bool m_use_new_font

Sets the usage of the font.

bool m_allow_two_perfedits

Enables the usage of two perfedit windows, for added convenience in editing multi-set songs.

• int m_h_perf_page_increment

Allows a changed to the page size for the horizontal scroll bar.

int m_v_perf_page_increment

Allows a changed to the page size for the vertical scroll bar.

· int m_progress_bar_colored

If set, makes progress bars have the "progress_color()", instead of black.

bool m_progress_bar_thick

If set, makes progress bars thicker than 1 pixel...

· bool m inverse colors

If set, use an alternate, neo-inverse color palette.

int m_window_redraw_rate_ms

Provides the global setting for redraw rate of windows.

• int m_text_x

Constants for the mainwid class.

- int m text y
- · int m_seqchars_x

Constants for the mainwid class.

- int m seqchars y
- int m_midi_ppqn

Provides the universal PPQN setting for the duration of this setting.

int m_midi_beats_per_measure

Provides the universal and unambiguous MIDI value for beats per measure, also called "beats per bar" (BPB).

• int m_midi_beats_per_minute

Provides the universal and unambiguous MIDI value for beats per minute (BPM).

int m_midi_beat_width

Provides the universal MIDI value for beats width (BW).

· char m_midi_buss_override

Provides a universal override of the buss number for all sequences, for the purpose of convenience of of testing.

- · int m total segs
- int m_seqs_in_set

Number of patterns/sequences in the Patterns Panel, also known as a "set" or "screen set".

• int m_gmute_tracks

Number of group-mute tracks that can be supported, which is m_seqs_in_set squared, or 1024.

int m_max_sequence

The maximum number of patterns supported is given by the number of patterns supported in the panel (32) times the maximum number of sets (32), or 1024 patterns.

• int m_seqarea_x

The m_seqarea_x and m_seqarea_y constants are derived from the width and heights of the default character set, and the number of characters in width, and the number of lines, in a pattern/sequence box.

- · int m segarea y
- int m_seqarea_seq_x

Area of what? Doesn't look at all like it is based on the size of characters.

- int m_seqarea_seq_y
- · int m mainwid x

The width of the main pattern/sequence grid, in pixels.

- int m_mainwid_y
- · bool m save user config

Provides a temporary variable that can be set from the command line to cause the "user" state to be saved into the "user" configuration file.

· const int mc min zoom

Provides the minimum zoom value, currently a constant.

• const int mc_max_zoom

Provides the maximum zoom value, currently a constant.

const int mc_baseline_ppqn

Permanent storage for the baseline, default PPQN used by Seq24.

Friends

class userfile

12.74.1 Detailed Description

These settings will eventually be made part of the "user" settings file.

12.74.2 Member Typedef Documentation

12.74.2.1 typedef std::vector<user_midi_bus> seq64::user_settings::Busses [private]

Internal type for the container of user_midi_bus objects. Sorry about the "confusion" about "bus" versus "buss". See Google for arguments about it.

- 12.74.2.2 typedef std::vector<user midi bus>::iterator seq64::user settings::BussIterator [private]
- 12.74.2.3 typedef std::vector<user_midi_bus>::const_iterator seq64::user_settings::BussConstIterator [private]
- 12.74.2.4 typedef std::vector<user instrument> seq64::user settings::Instruments [private]

Internal type for the container of user_instrument objects.

- 12.74.2.6 typedef std::vector<user_instrument>::const_iterator seq64::user_settings::InstrumentConstIterator [private]
- 12.74.3 Member Enumeration Documentation
- 12.74.3.1 enum seq64::user settings::mainwid grid style t [private]

Enumerator

grid_style_normal Provides a setting to control the overall style of grid-drawing for the pattern slots in mainwid. These values can be specified in the [user-interface-settings] section of the "user" configuration file.

```
The grid background color is the normal background color for the current GTK theme. The box is drawn with brackets on either side.
```

grid_style_white The grid background color is white. This style better fits displaying the white-on-black sequence numbers. The box is drawn with brackets on either side.

grid_style_black The grid background color is black.

grid_style_max Marks the end of the list, and is an illegal value.

12.74.4 Constructor & Destructor Documentation

- 12.74.4.1 seq64::user_settings::user_settings()
- 12.74.4.2 seq64::user_settings::user_settings (const user_settings & rhs)
- 12.74.5 Member Function Documentation
- 12.74.5.1 user_settings & seq64::user_settings::operator= (const user_settings & rhs)
- 12.74.5.2 void seq64::user_settings::set_defaults ()

For the m_midi_buses and m_instruments members, this function can only iterate over the current size of the vectors. But the default size is zero!

```
12.74.5.3 void seq64::user_settings::normalize ( )
12.74.5.4 bool seq64::user_settings::add_bus ( const std::string & alias )
12.74.5.5 bool seq64::user_settings::add_instrument ( const std::string & instname )
12.74.5.6 const user midi bus& seq64::user_settings::bus(int index) [inline]
Cannot append the const specifier.
12.74.5.7 const user instrument& seq64::user settings::instrument(int index) [inline]
Cannot append the const specifier.
12.74.5.8 int seq64::user_settings::bus_count() const [inline]
12.74.5.9 void seq64::user_settings::set_bus_instrument ( int index, int channel, int instrum )
12.74.5.10 int seq64::user_settings::bus_instrument(int buss, int channel) [inline]
12.74.5.11 const std::string& seq64::user_settings::bus_name(int buss) [inline]
12.74.5.12 int seq64::user_settings::instrument_count() const [inline]
12.74.5.13 void seq64::user_settings::set_instrument_controllers ( int index, int cc, const std::string & ccname, bool isactive )
12.74.5.14 const std::string& seq64::user_settings::instrument_name(int instrum) [inline]
12.74.5.15 const std::string& seq64::user_settings::instrument_name( int buss, int channel ) [inline]
12.74.5.16 bool seq64::user_settings::instrument_controller_active (int instrum, int cc) [inline]
12.74.5.17 bool seq64::user_settings::controller_active(int buss, int channel, int cc) [inline]
It also has a shorter name.
12.74.5.18 const std::string& seq64::user_settings::instrument_controller_name( int instrum, int cc ) [inline]
12.74.5.19 const std::string& seq64::user_settings::controller_name ( int buss, int channel, int cc ) [inline]
It also has a shorter name.
```

```
12.74.5.20
          int seq64::user_settings::grid_style( ) const [inline]
12.74.5.21
          bool seq64::user_settings::grid_is_normal( ) const [inline]
12.74.5.22
          bool seq64::user_settings::grid_is_white( ) const [inline]
12.74.5.23
          bool seq64::user_settings::grid_is_black( ) const [inline]
12.74.5.24
          int seq64::user_settings::grid_brackets( ) const [inline]
12.74.5.25
          int seq64::user_settings::mainwnd_rows( ) const [inline]
12.74.5.26
          int seq64::user_settings::mainwnd_cols() const [inline]
12.74.5.27
          int seq64::user_settings::seqs_in_set( ) const [inline]
12.74.5.28
          int seq64::user_settings::gmute_tracks ( ) const [inline]
12.74.5.29
          int seq64::user_settings::max_sets() const [inline]
12.74.5.30
          int seq64::user_settings::max_sequence( ) const [inline]
12.74.5.31
          int seq64::user_settings::text_x ( ) const [inline]
12.74.5.32
          int seq64::user_settings::text_y( ) const [inline]
12.74.5.33
          int seq64::user_settings::seqchars_x ( ) const [inline]
12.74.5.34
          int seq64::user_settings::seqchars_y ( ) const [inline]
12.74.5.35
          int seq64::user_settings::seqarea_x ( ) const [inline]
12.74.5.36
          int seq64::user_settings::seqarea_y ( ) const [inline]
12.74.5.37
          int seq64::user_settings::seqarea_seq_x( ) const [inline]
12.74.5.38
          int seq64::user_settings::seqarea_seq_y ( ) const [inline]
12.74.5.39
          int seq64::user_settings::mainwid_border( ) const [inline]
12.74.5.40
          int seq64::user_settings::mainwid_spacing( ) const [inline]
12.74.5.41
          int seq64::user_settings::mainwid_x( ) const [inline]
12.74.5.42 int seq64::user_settings::mainwid_y( ) const [inline]
12.74.5.43 int seq64::user_settings::control_height() const [inline]
12.74.5.44 int seq64::user_settings::zoom() const [inline]
12.74.5.45 void seq64::user_settings::zoom ( int value )
```

The default value is 2. Note that 0 is allowed as a special case, which allows the default zoom to be adjusted when the PPQN value is different from the default.

```
12.74.5.46 bool seq64::user_settings::global_seq_feature( ) const [inline]
12.74.5.47 void seq64::user_settings::global_seq_feature( bool flag ) [inline]
12.74.5.48 int seq64::user_settings::seqedit_scale() const [inline]
12.74.5.49 void seq64::user_settings::seqedit_scale ( int scale ) [inline]
12.74.5.50 int seq64::user_settings::seqedit_key( ) const [inline]
12.74.5.51 void seq64::user_settings::seqedit_key ( int key ) [inline]
12.74.5.52 int seq64::user_settings::seqedit_bgsequence( ) const [inline]
12.74.5.53 void seq64::user_settings::seqedit_bgsequence(int seqnum) [inline]
12.74.5.54 bool seq64::user_settings::use_new_font() const [inline]
12.74.5.55 bool seq64::user_settings::allow_two_perfedits() const [inline]
12.74.5.56 int seq64::user_settings::perf_h_page_increment() const [inline]
12.74.5.57 int seq64::user_settings::perf_v_page_increment( ) const [inline]
12.74.5.58
          int seq64::user_settings::progress_bar_colored( ) const [inline]
12.74.5.59 bool seq64::user_settings::progress_bar_thick( ) const [inline]
12.74.5.60 bool seq64::user_settings::inverse_colors() const [inline]
12.74.5.61 int seq64::user_settings::window_redraw_rate( ) const [inline]
12.74.5.62 bool seq64::user_settings::save_user_config() const [inline]
12.74.5.63 void seq64::user_settings::save_user_config ( bool flag ) [inline]
12.74.5.64 void seq64::user_settings::grid_brackets (int thickness) [inline], [protected]
12.74.5.65 void seq64::user_settings::grid_style ( int gridstyle ) [protected]
12.74.5.66 void seq64::user_settings::mainwnd_rows ( int value ) [protected]
```

The default value is 4. Dependent values are recalculated after the assignment.

```
12.74.5.67 void seq64::user_settings::mainwnd_cols(int value) [protected]
```

The default value is 8. Dependent values are recalculated after the assignment.

```
12.74.5.68 void seq64::user_settings::max_sets (int value) [protected]
```

The default value is 32. Dependent values are recalculated after the assignment.

```
12.74.5.69 void seq64::user_settings::text_x ( int value ) [protected]
```

The default value is 6. Dependent values are recalculated after the assignment. This value is currently restricted, until we can code up a bigger font.

```
12.74.5.70 void seq64::user_settings::text_y ( int value ) [protected]
```

The default value is 12. Dependent values are recalculated after the assignment. This value is currently restricted, until we can code up a bigger font.

```
12.74.5.71 void seq64::user_settings::seqchars_x ( int value )  [protected]
12.74.5.72 void seq64::user_settings::seqchars_y ( int value )  [protected]
12.74.5.73 void seq64::user_settings::seqarea_x ( int value )  [protected]
12.74.5.74 void seq64::user_settings::seqarea_y ( int value )  [protected]
12.74.5.75 void seq64::user_settings::seqarea_seq_x ( int value )  [protected]
12.74.5.76 void seq64::user_settings::seqarea_seq_y ( int value )  [protected]
12.74.5.77 void seq64::user_settings::mainwid_border ( int value )  [protected]
```

The default value is 0. Dependent values are recalculated after the assignment.

```
12.74.5.78 void seq64::user_settings::mainwid_spacing (int value) [protected]
```

The default value is 2. Dependent values are recalculated after the assignment.

```
12.74.5.79 void seq64::user_settings::control_height( int value ) [protected]
```

The default value is 0. Dependent values are recalculated after the assignment.

```
12.74.5.80 void seq64::user_settings::dump_summary() [protected]
```

Does its work only if PLATFORM_DEBUG and SEQ64_USE_DEBUG_OUTPUT are defined. Only enabled in emergencies :-D.

```
12.74.5.81 int seq64::user_settings::midi_ppqn() const [inline]

12.74.5.82 int seq64::user_settings::midi_beats_per_bar() const [inline]

12.74.5.83 int seq64::user_settings::midi_beats_per_minute() const [inline]

12.74.5.84 int seq64::user_settings::midi_beat_width() const [inline]

12.74.5.85 char seq64::user_settings::midi_buss_override() const [inline]

12.74.5.86 int seq64::user_settings::min_zoom() const [inline]

12.74.5.87 int seq64::user_settings::max_zoom() const [inline]

12.74.5.88 int seq64::user_settings::baseline_ppqn() const [inline]

12.74.5.89 void seq64::user_settings::use_new_font(bool flag) [inline]

12.74.5.90 void seq64::user_settings::allow_two_perfedits(bool flag) [inline]
```

This value ranges from 1 (the original value, really too small for a "page" operation) to 6 (which is 24 measures, the same as the typical width of the perfroll)

```
12.74.5.92 void seq64::user_settings::perf_v_page_increment ( int inc )
```

This value ranges from 1 (the original value, really too small for a "page" operation) to 18 (which is 18 tracks, slightly more than the typical height of the perfroll)

```
12.74.5.93 void seq64::user_settings::progress_bar_colored ( int palcode ) [inline]
12.74.5.94 void seq64::user_settings::progress_bar_thick ( bool flag ) [inline]
12.74.5.95 void seq64::user_settings::inverse_colors ( bool flag ) [inline]
12.74.5.96 void seq64::user_settings::window_redraw_rate ( int ms ) [inline]
12.74.5.97 void seq64::user_settings::midi_ppqn ( int value )
```

The default value is 192.

```
12.74.5.98 void seq64::user_settings::midi_buss_override ( char buss )
```

The default value is -1, which means that there is no buss override. It provides a way to override the buss number for smallish MIDI files. It replaces the buss-number read from the file. This option is turned on by the –bus option, and is merely a convenience feature for the quick previewing of a tune. (It's called "developer laziness".)

```
12.74.5.99 void seq64::user_settings::midi_beats_per_bar( int value ) [protected]
```

The default value is 4.

```
12.74.5.100 void seq64::user_settings::midi_beats_per_minute( int value) [protected]
```

The default value is 120.

```
12.74.5.101 void seq64::user_settings::midi_beat_width(int bw) [protected]
```

The default value is 4.

```
12.74.5.102 user_midi_bus & seq64::user_settings::private_bus(int index) [private]
```

This invalid object has an empty alias, and all the instrument numbers are -1.

```
12.74.5.103 user_instrument & seq64::user_settings::private_instrument(int index) [private]
```

This invalid object has an empty(), instrument name, false for all controllers_active[] values, and empty controllers[] string values.

12.74.6 Friends And Related Function Documentation

```
12.74.6.1 friend class userfile [friend]
```

12.74.7 Field Documentation

```
12.74.7.1 Busses seq64::user_settings::m_midi_buses [private]
```

Since this object is a vector, its size is adjustable.

```
12.74.7.2 Instruments seq64::user_settings::m_instruments [private]
```

The size is adjustable, and grows as objects are added.

```
12.74.7.3 mainwid_grid_style_t seq64::user_settings::m_grid_style [private]
```

These are not labelled, but are present in the "user" configuration file in the following order:

```
-# grid-style
-# grid-brackets
   mainwnd-rows
   mainwnd-cols
-# max-set
-# mainwid-border
-#
   control-height
-# global-seq-feature
-# use-new-font
-# allow-two-perfedits
-# perf-h-page-increment
-#
   perf-v-page-increment
-# progress-bar-colored (new)
-# progress-bar-thick (new)
   window-redraw-rate-ms (new)
```

Specifies the current grid style.

```
12.74.7.4 int seq64::user_settings::m_grid_brackets [private]
```

0 = no brackets, 1 and above is the thickness of the brakets. 1 is the normal thickness of the brackets, 2 is a two-pixel thickness, and so on.

```
12.74.7.5 int seq64::user_settings::m_mainwnd_rows [private]
```

The current value is 4, and if changed, many other values depend on it. Together with m_mainwnd_cols, this value fixes the patterns grid into a 4 x 8 set of patterns known as a "screen set". We would like to be able to change this value from 4 to 8, and maybe allow the values of 5, 6, and 7 as well. But if we could just get 8 working, then well would Sequencer64 deserve the 64 in its name.

```
12.74.7.6 int seg64::user_settings::m_mainwnd_cols [private]
```

The current value is 4, and probably won't change, since other values depend on it. Together with m_mainwnd_rows, this value fixes the patterns grid into a 4 x 8 set of patterns known as a "screen set".

```
12.74.7.7 int seq64::user_settings::m_max_sets [private]
```

Basically, that the number of times the Patterns Panel can be filled. 32 sets can be created. Although this value is part of the "user" configuration file, it is likely that it will never change. Rather, the number of sequences per set would change. We'll see.

```
12.74.7.8 int seq64::user_settings::m_mainwid_border [private]
```

We'll try changing them and see what happens. Increasing these value spreads out the pattern grids a little bit and makes the Patterns panel slightly bigger. Seems like it would be useful to make these values user-configurable.

```
12.74.7.9 int seq64::user_settings::m_mainwid_spacing [private]
```

```
12.74.7.10 int seq64::user_settings::m_control_height [private]
```

But it is used only in this header file, to define m_mainwid_y, but doesn't add anything to that value.

```
12.74.7.11 int seq64::user_settings::m_current_zoom [private]
```

The original default value was 32 ticks per pixel, but larger PPQN values need higher values, and we will have to adapt the default zoom to the PPQN value. Also, the zoom can never be zero, as it can appear as the divisor in scaling equations.

```
12.74.7.12 bool seq64::user_settings::m_global_seq_feature_save [private]
```

In this feature, applying one of these three changes to a sequence causes them to also be applied to sequences that are subsequently opened for editing. However, we improve on this feature by allowing the changes to be saved in the global, proprietary part of the saved MIDI file.

If false, the user can still save the key/scale/background-sequence values with each individual sequence, so they can be different.

This value will be true by default, unless changed in the "user" configuration file.

```
12.74.7.13 int seq64::user_settings::m_seqedit_scale [private]
```

Its default value is c_scale_off. Although this value is now stored in the user_settings class, it always comes from the currently loaded MIDI file, if present. If m_global_seq_feature_save is true, this variable is stored in the "proprietary" track at the end of the file, under the control tag c_musicscale, and will be applied to any sequence that is edited. If m_global_seq_feature_save is false, this variable is stored, if used, in the meta-data for the sequence to which it applies, and, again, is tagged with the control tag c_musicscale.

```
12.74.7.14 int seq64::user_settings::m_seqedit_key [private]
```

Its default value is SEQ64_KEY_OF_C. Although this value is now stored in the user_settings class, it always comes from the currently loaded MIDI file, if present. If m_global_seq_feature_save is true, this variable is stored in the "proprietary" track at the end of the file, under the control tag c_musickey, and will be applied to any sequence that is edited. If m_global_seq_feature_save is false, this variable is stored, if used, in the meta-data for the sequence to which it applies, and, again, is tagged with the control tag c_musickey.

```
12.74.7.15 int seq64::user_settings::m_seqedit_bgsequence [private]
```

Its default value is SEQ64_SEQUENCE_LIMIT. Although this value is now stored in the user_settings class, it always comes from the currently loaded MIDI file, if present. If m_global_seq_feature_save is true, this variable is stored, if it has a valid (but not "legal") value, in the "proprietary" track at the end of the file, under the control tag c_backsequence, and will be applied to any sequence that is edited. If m_global_seq_feature_save is false, this variable is stored, if used, in the meta-data for the sequence to which it applies, and, again, is tagged with the control tag c_backsequence.

```
12.74.7.16 bool seq64::user_settings::m_use_new_font [private]
```

By default, in normal mode, the new font is used. In legacy mode, the old font is used.

```
12.74.7.17 bool seq64::user_settings::m_allow_two_perfedits [private]
```

Defaults to true.

```
12.74.7.18 int seq64::user_settings::m_h_perf_page_increment [private]
```

The value used to be hardwired to 1 (in four-measure units), now it defaults to 4 (16 measures at a time). The value of 1 is already covered by the scrollbar arrows.

```
12.74.7.19 int seq64::user_settings::m_v_perf_page_increment [private]
```

The value used to be hardwired to 1 (in single-track units), now it defaults to 8. The value of 1 is already covered by the scrollbar arrows.

```
12.74.7.20 int seq64::user_settings::m_progress_bar_colored [private]
```

This value is no longer hardwired in the gui_palette_gtk2 module to be red. Now we want to let the color select from a slightly large palette. We chande this from a boolean to an integer to allow the selection of more colors.

```
12.74.7.21 bool seq64::user_settings::m_progress_bar_thick [private]
```

2 pixels. It isn't useful to support anything thicker.

```
12.74.7.22 bool seq64::user_settings::m_inverse_colors [private]
```

Not all colors are reversed, though.

```
12.74.7.23 int seq64::user_settings::m_window_redraw_rate_ms [private]
```

Not all windows use this yet. The default is 40 ms (c_redraw_ms, which is 20 ms in Windows builds)), but some windows originally used 25 ms, so beware of side-effects.

```
12.74.7.24 int seq64::user_settings::m_text_x [private]
```

The m_text_x and m_text_y constants help define the "seqarea" size. It looks like these two values are the character width (x) and height (y) in pixels. Thus, these values would be dependent on the font chosen. But that, currently, is hard-wired. See the m_font_6_12[] array for the default font specification.

However, please not that font files are not used. Instead, the fonts are provided by two pixmaps in the src/pixmap directory: font_b.xpm (black lettering on a white background) and font_w.xpm (white lettering on a black background).

We have added black-on-yellow and yellow-on-black versions of the fonts, to support the highlighting of pattern boxes if they are empty of actual MIDI events.

We have also added a set of four new font files that are roughly the same size, and are treated as the same size, but look smooth and less like a DOS-era font.

The font module does not use these values directly, but does define some similar variables that differ slightly between the two styles of font. There are a lot of tricks and hard-wired places to fix before further work can be done with fonts in Sequencer64.

```
12.74.7.25 int seq64::user_settings::m_text_y [private]
12.74.7.26 int seq64::user settings::m seqchars x [private]
```

The m_seqchars_x and m_seqchars_y constants help define the "seqarea" size. These look like the number of characters per line and the number of lines of characters, in a pattern/sequence box.

```
12.74.7.27 int seq64::user_settings::m_seqchars_y [private]
12.74.7.28 int seq64::user_settings::m_midi_ppqn [private]
```

This variable replaces the global ppqn. The default value of this setting is 192 parts-per-quarter-note (PPQN). There is still a lot of work to get a different PPQN to work properly in speed of playback, scaling of the user interface, and other issues. Note that this value can be changed by the still-experimental –ppqn option. There is one remaining trace of the global, though: DEFAULT_PPQN.

```
12.74.7.29 int seq64::user_settings::m_midi_beats_per_measure [private]
```

This variable will replace the global beats per measure. The default value of this variable is SEQ64_DEFAULT_← BEATS_PER_MEASURE (4). For external access, we will call this value "beats per bar", abbreviate it "BPB", and use "bpb" in any accessor function names. Now, although it applies to the whole session, we should be able to continue seq24's tradition of allowing each sequence to have its own time signature. Also, there are a number of places where the number 4 appears and looks like it might be a hardwired BPB value, either for MIDI purposes or for drawing the piano-roll grids. So we might need a couple different versions of this variable.

```
12.74.7.30 int seq64::user_settings::m_midi_beats_per_minute [private]
```

This variable will replace the global beats per minute. The default value of this variable is DEFAULT_BPM (120). This variable should apply to the whole session; there's probably no way to support a diffent tempo for each sequence. But we shall see. For external access, we will call this value "beats per minute", abbreviate it "BPM", and use "bpm" in any accessor function names.

```
12.74.7.31 int seq64::user_settings::m_midi_beat_width [private]
```

This variable will replace the global beat_width. The default value of this variable is DEFAULT_BEAT_WIDTH (4). Now, although it applies to the whole session, we should be able to continue seq24's tradition of allowing each sequence to have its own time signature. Also, there are a number of places where the number 4 appears and looks like it might be a hardwired BW value, either for MIDI purposes or for drawing the user-interface. So we might need a couple different versions of this variable. For external access, we will call this value "beat width", abbreviate it "BW", and use "bw" in any accessor function names.

```
12.74.7.32 char seq64::user_settings::m_midi_buss_override [private]
```

This variable replaces the global buss-override variable, and is set via the command-line option -bus.

```
12.74.7.33 int seq64::user_settings::m_total_seqs [private]
```

12.74.7.34 int seq64::user_settings::m_seqs_in_set [private]

This value is $4 \times 8 = 32$ by default.

Warning

Currently implicit/explicit in a number of the "rc" file and rc_settings. Would probably want the left 32 or the first 32 items in the main window only to be subject to keystroke control. This value is calculated by the normalize() function, and is *not* part of the "user" configuration file.

```
12.74.7.35 int seq64::user_settings::m_gmute_tracks [private]
```

This value is *not* part of the "user" configuration file; it is calculated by the normalize() function.

```
12.74.7.36 int seq64::user_settings::m_max_sequence [private]
```

It is a derived value, and not stored in the "user" file.

```
m_max_sequence = m_seqs_in_set * m_max_sets;
```

```
12.74.7.37 int seq64::user_settings::m_seqarea_x [private]
```

Compare these two constants to m_seqarea_seq_x(y), which was in mainwid.h, but is now in this file.

```
12.74.7.38 int seq64::user_settings::m_seqarea_y [private]
```

12.74.7.39 int seq64::user_settings::m_seqarea_seq_x [private]

These are used only in the mainwid module.

```
12.74.7.40 int seq64::user_settings::m_seqarea_seq_y [private]
```

```
12.74.7.41 int seq64::user_settings::m_mainwid_x [private]
```

Affected by the m_mainwid_border and m_mainwid_spacing values.

```
12.74.7.42 int seq64::user_settings::m_mainwid_y [private]
```

```
12.74.7.43 bool seq64::user_settings::m_save_user_config [private]
```

Normally, this state is not saved. It is not saved because there is currently no user-interface for editing it, and because it can pick up some command-line options, and it is not right to have them written to the "user" configuration file.

(The "rc" configuration file is a different case, having historically always been saved, and having a number of command-line options, such as JACK settings that should generally be permanent on a given system.)

Anyway, this flag can be set by the –user-save option. This setting is never saved. But note that, if no "user" configuration file is found, it is then saved anyway.

```
12.74.7.44 const int seq64::user_settings::mc_min_zoom [private]
```

It's value is 1.

```
12.74.7.45 const int seq64::user_settings::mc_max_zoom [private]
```

It's value was 32, but is now 512, to allow for better presentation of high PPQN valued sequences.


```
12.74.7.46 const int seq64::user_settings::mc_baseline_ppqn [private]
```

This value is necessary in order to keep user-interface elements stable when different PPQNs are used. It is set to DEFAULT_PPQN.

12.75 seq64::userfile Class Reference

Supports the user's \sim /.config/sequencer64/sequencer64.usr and \sim /.seq24usr configuration file

Inheritance diagram for seq64::userfile:



Public Member Functions

• userfile (const std::string &a_name)

Principal constructor.

• ∼userfile ()

A rote destructor needed for a derived class.

• bool parse (perform &a_perf)

Parses a "usr" file, filling in the given perform object.

bool write (const perform &a_perf)

This function just returns false, as there is no "perform" information in the user-file yet.

Private Member Functions

void dump_setting_summary ()

Provides a debug dump of basic information to help debug a surprisingly intractable problem with all busses having the name and values of the last buss in the configuration.

Additional Inherited Members

12.75.1 Constructor & Destructor Documentation

12.75.1.1 seq64::userfile::userfile (const std::string & name)

Parameters

	name	Provides the full file path specification to the configuration file.	
--	------	--	--

12.75.1.2 seq64::userfile:: \sim userfile ()

12.75.2 Member Function Documentation

12.75.2.1 bool seq64::userfile::parse (perform & a_perf) [virtual]

This function opens the file as a text file (line-oriented).

Parameters

|--|

Returns

Returns true if the parsing succeeded.

Implements seq64::configfile.

12.75.2.2 bool seq64::userfile::write (const perform & a_perf) [virtual]

Parameters

a_perf	The performance object, currently unused.
a_pen	The penormance object, currently unused.

Returns

Returns true if the writing succeeded.

Implements seq64::configfile.

12.75.2.3 void seq64::userfile::dump_setting_summary() [private]

Does work only if PLATFORM_DEBUG is defined; see the user_settings class.

Index

\sim AbstractPerfInput	seq64::midi_splitter, 298
seq64::AbstractPerfInput, 86	\sim midi_vector
\sim automutex	seq64::midi_vector, 305
seq64::automutex, 87	\sim midibus
\sim configfile	seq64::midibus, 309
seq64::configfile, 94	\sim midifile
~editable_event	seq64::midifile, 316
seq64::editable_event, 100	\sim optionsfile
~editable events	seq64::optionsfile, 335
seq64::editable_events, 108	\sim perfedit
~event	seq64::perfedit, 342
seq64::event, 116	\sim perfnames
~event_list	seq64::perfnames, 350
seq64::event_list, 130	\sim perform
~eventedit	seq64::perform, 367
seq64::eventedit, 140	\sim perfroll
~eventslots	seq64::perfroll, 411
seq64::eventslots, 151	\sim perftime
~gui_assistant	seq64::perftime, 423
seq64::gui_assistant, 173	\sim seqdata
~gui_assistant_gtk2	seq64::seqdata, 448
seq64::gui_assistant_gtk2, 175	\sim seqedit
~gui_drawingarea_gtk2	seq64::seqedit, 460
seq64::gui_drawingarea_gtk2, 179	\sim seqevent
~gui_palette_gtk2	seq64::seqevent, 475
	\sim seqkeys
seq64::gui_palette_gtk2, 192 ~gui_window_gtk2	seq64::seqkeys, 485
	\sim seqmenu
seq64::gui_window_gtk2, 196	seq64::seqmenu, 494
~jack_assistant	\sim seqroll
seq64::jack_assistant, 201	seq64::seqroll, 504
~keys_perform	\sim seqtime
seq64::keys_perform, 222	seq64::seqtime, 521
~keys_perform_gtk2	\sim sequence
seq64::keys_perform_gtk2, 234	seq64::sequence, 534
~lfownd	\sim triggers
seq64::Ifownd, 243	seq64::triggers, 573
~maintime	\sim userfile
seq64::maintime, 247	seq64::userfile, 611
~mainwid	
seq64::mainwid, 252	about_dialog
~mainwnd	seq64::mainwnd, 267
seq64::mainwnd, 264	AbstractPerfInput
~mastermidibus	seq64::AbstractPerfInput, 86
seq64::mastermidibus, 276	active
~midi_container	seq64::midi_control, 291
seq64::midi_container, 285	add
~midi_list	seq64::editable_events, 109, 110
seq64::midi_list, 294	seq64::event_list, 131
\sim midi_splitter	seq64::triggers, 575

add_bus	allow_two_perfedits
seq64::user_settings, 598	seq64::user_settings, 600, 602
add event	analyze
seq64::midi_container, 287	seq64::editable_event, 103
seq64::sequence, 541, 553	any_group_unmutes
	seq64::perform, 377
add_instrument	any_selected_notes
seq64::user_settings, 598	seq64::event_list, 134
add_jack_sync_page	· —
seq64::options, 333	seq64::sequence, 534
add_keyboard_page	append_sysex
seq64::options, 333	seq64::event, 122, 123
add_long	apply_length
seq64::midi_container, 287	seq64::seqedit, 462
add_midi_clock_page	at_bpm_dn
seq64::options, 333	seq64::keys_perform, 228
add_midi_input_page	at_bpm_up
seq64::options, 333	seq64::keys_perform, 228
add_mouse_page	at_event_edit
seq64::options, 333	seq64::keys_perform, 230
add_note	at_group_learn
seq64::seqroll, 504	seq64::keys_perform, 229
seq64::sequence, 553	at_group_off
add_sequence	seq64::keys_perform, 229
seq64::perform, 370	at_group_on
add_short	seq64::keys_perform, 229
seq64::midi_container, 287	at_keep_queue
add_trigger	seq64::keys_perform, 229
seq64::midifile, 320	at_pattern_edit
seq64::sequence, 542	seq64::keys_perform, 230
add_variable	at_pause
	seq64::keys_perform, 230
seq64::midi_container, 286	at_queue
adding	seq64::keys_perform, 229
seq64::seqroll, 513	at_replace
adj_callback_bpm	seq64::keys_perform, 228
seq64::mainwnd, 265	at screenset dn
adj_callback_ss	seq64::keys perform, 229
seq64::mainwnd, 265	at screenset up
adjust_offset	seq64::keys_perform, 229
seq64::sequence, 563	at_set_playing_screenset
seq64::triggers, 580	seq64::keys_perform, 229
adjust_offsets_to_length	at_show_ui_sequence_key
seq64::triggers, 575	seq64::keys_perform, 230
adjust_timestamp	at_show_ui_sequence_number
seq64::sequence, 552	seq64::keys_perform, 230
adjust_trigger_offsets_to_length	
seq64::sequence, 563	at_snapshot_1
adjustment dummy	seq64::keys_perform, 229
seq64, 74	at_snapshot_2
alias	seq64::keys_perform, 229
seq64::user_midi_bus_t, 589	at_start
align_selection	seq64::keys_perform, 230
seq64::seqroll, 511	at_stop
all_notes_off	seq64::keys_perform, 230
seq64::perform, 379	auto_option_save
allow_mod4_mode	seq64::rc_settings, 432, 434
seq64::rc_settings, 432, 434	automutex
	seq64::automutex, 87
allow_snap_split	BLACK ON CVAN
seq64::rc_settings, 432, 434	BLACK_ON_CYAN

seq64::font, 161	seq64::seqroll, 511
BLACK_ON_YELLOW	button_press_initial
seq64::font, 161	seq64::seqroll, 511
BLACK	button_release seq64::seqroll, 511
seq64::font, 161 background_sequence	sequ4seqioli, 311
seq64::sequence, 561	c_backsequence
baseline_ppqn	seq64, 79
seq64::user settings, 602	c_bpmtag
beat width	seq64, 79
seq64::midi_timing, 302	c_chord_text
beats	seq64, 82
seq64::midi_measures, 296	c_compress_pattern
beats_per_measure	seq64, 55 c_controller_names
seq64::midi_timing, 302	seq64, 75
beats_per_minute	c_expand_pattern
seq64::midi_timing, 302	seq64, 55
beats_per_minute_from_tempo_us	c_interval_text
seq64, 61	seq64, 82
begin	c_key_text
seq64::editable_events, 109	seq64, 82
seq64::event_list, 130 bg_color	c_mainwid_x
seq64::gui_palette_gtk2, 193	seq64, 84
black	c_mainwid_y
seq64::gui_palette_gtk2, 192	seq64, 84
black_key	c_max_busses
seq64::gui_palette_gtk2, 193	seq64, 82
black_paint	c_max_instruments
seq64::gui_palette_gtk2, 193	seq64, 82 c_midi_control_bpm_dn
blue	seq64, 80
seq64::gui_palette_gtk2, 193	c_midi_control_bpm_up
bpm_dn	seq64, 79
seq64::keys_perform, 223	c_midi_control_mod_glearn
bpm_up	seq64, 80
seq64::keys_perform, 223	c_midi_control_mod_gmute
build_details	seq64, 80
seq64, 67	c_midi_control_mod_queue
bus seq64::user_settings, 598	seq64, 80
bus count	c_midi_control_mod_replace
seq64::user_settings, 598	seq64, 80
bus instrument	c_midi_control_mod_snapshot seq64, 80
seq64::user_settings, 598	c_midi_control_play_ss
bus_name	seq64, 80
seq64::user_settings, 598	c_midi_control_ss_dn
BussConstIterator	seq64, 80
seq64::user_settings, 597	c_midi_control_ss_up
BussIterator	seq64, 80
seq64::user_settings, 597	c_midi_controls
bussbyte	seq64, 80
seq64, 51	c_midi_track_ctrl
Busses	seq64, 79
seq64::user_settings, 597	c_midibus
button	seq64, 78
seq64::click, 90	c_midibus_input_size seq64, 77
seq64::options, 332 button_press	c_midibus_output_size
	o_maiodo_odipdi_size

04.77	04.55
seq64, 77	seq64, 55
c_midibus_sysex_chunk	c_select_all_notes
seq64, 77	seq64, 55
c_midich	c_select_even_notes
seq64, 78	seq64, 55
c_midiclocks	c_select_inverse_events
seq64, 79	seq64, 55
c_midictrl	c_select_inverse_notes
seq64, 79	seq64, 55
c_music_scales	c_select_odd_notes
seq64, 53	seq64, 55
c_musickey	c_status_queue
seq64, 79	seq64, 84
c_musicscale	c_status_replace
seq64, 79	seq64, 83
c_mutegroups	c_status_snapshot
seq64, 79	seq64, 84
c_notes	c_swing_notes
seq64, 79	seq64, 55
c_perf_bp_mes	c_tighten_events
seq64, 79	seq64, 55
c_perf_bw	c_tighten_notes
seq64, 79	seq64, 55
c_quantize_events	c_timesig
seq64, 55	seq64, 79
c_quantize_notes	c_transpose
seq64, 55	seq64, 79
c_reserved	c_transpose_h
seq64, 55	seq64, 55
c_scale_blues	c_transpose_notes
seq64, 54	seq64, 55
c_scale_c_whole_tone	c_triggers
seq64, 54	seq64, 79
c_scale_harmonic_minor	c_triggers_new
seq64, 54	seq64, 79
c_scale_major	CYAN_ON_BLACK
seq64, 54	seq64::font, 161
c_scale_major_pentatonic	calculate_base_sizes
seq64, 54	seq64::mainwid, 255
c_scale_melodic_minor	category
seq64, 54	seq64::editable_event, 101, 102
c_scale_minor	category_channel_message
seq64, 54	seq64::editable_event, 99
c_scale_minor_pentatonic	category_meta_event
seq64, 54	seq64::editable_event, 99
c_scale_off	category_name
seq64, 54	seq64::editable_event, 99
c_scale_size	category_prop_event
seq64, 54	seq64::editable_event, 99
c_scales_policy	category_string
seq64, 80	seq64::editable_event, 101
c_scales_text	category_system_message
seq64, 81	seq64::editable_event, 99
c_scales_transpose_dn	category_t
seq64, 81	seq64::editable_event, 99
c_scales_transpose_up	change_event_data_range
seq64, 80	seq64::sequence, 554
c_select_all_events	change_focus

seq64::eventedit, 142	clear_links
seq64::seqedit, 466	seq64::event_list, 133
change_horz	clear_old
seq64::perfroll, 413	seq64::seqroll, 512
seq64::perftime, 423	clear_selected
seq64::seqdata, 449	seq64::seqroll, 512
seq64::seqevent, 478	clear_sequence_triggers
seq64::seqroll, 509	seq64::perform, 371
seq64::seqtime, 522	clear_triggers
change_vert	seq64::sequence, 547
seq64::eventslots, 156	clear_window
seq64::perfnames, 351	seq64::gui_drawingarea_gtk2, 180
seq64::perfroll, 413	click
seq64::seqkeys, 487	seq64::click, 89
seq64::seqroll, 509	client
channel_count	seq64::jack_assistant, 206
seq64::user_midi_bus, 588	client_name
channel_match	seq64::jack_assistant, 206
seq64::sequence, 564	client_open
channel_max	seq64::jack_assistant, 207
seq64::user_midi_bus, 588	client_uuid
channel_string	seq64::jack_assistant, 206
seq64::editable_event, 103	clip_timestamp
char_height	seq64::sequence, 552
seq64::font, 162	clock
char_width	seq64::mastermidibus, 278
seq64::font, 162	seq64::midibus, 310
CharList	clock_callback_mod
seq64::midi_list, 294 CharVector	seq64::options, 332 clock_callback_off
seq64::midi_vector, 305	seq64::options, 332 clock_callback_on
check_channel seq64::event, 118	seq64::options, 332
check queued tick	clock e
seg64::sequence, 539	seq64, 53
checklen	clock_mod_callback
seg64::midifile, 320	seq64::options, 332
choose file	clock_tick_duration_bogus
seq64::mainwnd, 269	seq64, 63
choose_ppqn	clock_ticks_from_ppqn
seq64, 73	seq64, 64
clamp	clocks_per_metronome
seq64, 75	seq64::perform, 369
clamp_track	seq64::sequence, 536, 537
seq64::perform, 397	close_out
clear	seq64::eventedit, 143
seq64::editable_events, 110	collapse
seq64::event_list, 132	seq64::perfedit, 344
seq64::midi_container, 286	seq64::perform, 374
seq64::midi_list, 295	Color
seq64::midi_vector, 306	seq64::font, 161
seq64::triggers, 580	seq64::gui_palette_gtk2, 191
clear_all	complete_paste
seq64::perform, 370	seq64::seqroll, 507
clear_flags	condition var
seq64::seqroll, 512	seq64::condition_var, 92
clear link	config directory
seq64::event, 123	seq64::rc_settings, 433, 435
•	5 , ,

config_filename	copy_selected
seq64::rc_settings, 433, 435	seq64::sequence, 549
config_filename_alt	seq64::triggers, 577
seq64::rc_settings, 433, 436	copy_selected_trigger
config_filespec	seq64::sequence, 545
seq64::rc_settings, 432	copy_triggers
configfile	seq64::perform, 373
seq64::configfile, 94	seq64::sequence, 547
const_iterator	count
seq64::editable events, 107	seq64::editable_events, 109
seq64::event_list, 130	seq64::event_list, 131
continue_from	seq64::midi_splitter, 299
seq64::mastermidibus, 278	count_selected_events
seq64::midibus, 310	seq64::event_list, 134
control_height	count_selected_notes
seq64::user_settings, 599, 601	seq64::event_list, 134
controller_active	create_lash_driver
seq64::user_instrument, 584	seq64, 72
seq64::user_settings, 598	create_menu_image
controller_count	seq64::seqedit, 466
seq64::user_instrument, 584	create_menus
controller_max	seq64::seqedit, 464
seq64::user_instrument, 584	current_event
controller_name	seq64::editable_events, 110
seq64::user_instrument, 584	current index
seq64::user_settings, 598	seq64::eventslots, 151
controllers	current_screen_set_notepad
	seq64::perform, 376
seq64::user_instrument_t, 585	current seq
controllers_active	seq64::seqmenu, 494
seq64::user_instrument_t, 586	current x
convert_sel_box_to_rect	seq64::gui_drawingarea_gtk2, 180
seq64::seqroll, 509	current y
convert_t	seq64::gui drawingarea gtk2, 180
seq64::seqevent, 478	cut_selected
convert_tn	seq64::sequence, 550
seq64::seqroll, 508	cut_selected_trigger
convert_tn_box_to_rect	seq64::sequence, 545
seq64::seqroll, 508	, ,
convert_x	DRAW_FIN
seq64::perfroll, 413	seq64, 54
seq64::seqdata, 449	DRAW_NORMAL_LINKED
seq64::seqevent, 478	seq64, 54
convert_xy	DRAW_NOTE_OFF
seq64::perfroll, 412	seq64, 54
seq64::seqroll, 508	DRAW_NOTE_ON
convert_y	seq64, 54
seq64::eventslots, 155	dark_blue
seq64::perfnames, 351	seq64::gui_palette_gtk2, 192
seq64::seqkeys, 487	dark_cyan
сору	seq64::gui_palette_gtk2, 192
seq64::perfedit, 344	dark_green
seq64::perform, 374	seq64::gui_palette_gtk2, 192
seq64::triggers, 579	dark_grey
copy_definitions	seq64::gui_palette_gtk2, 193
seq64::user_instrument, 585	dark_magenta
seq64::user_midi_bus, 588	seq64::gui_palette_gtk2, 192
copy_events	dark_orange
seq64::sequence, 562	seq64::gui_palette_gtk2, 192

dark_red	seq64::midi_container, 286
seq64::gui_palette_gtk2, 192	seq64::midi_list, 294
data	seg64::midi_vector, 305
seq64::event, 124	double_ticks_from_ppqn
seq64::midi_control, 291	seq64, 64
data_string	draw all
seq64::editable_event, 103	seq64::perfroll, 412
decrement_beats_per_minute	draw_area
seq64::perform, 390	seq64::seqkeys, 487
decrement_bottom	draw_background
seq64::eventslots, 157	seq64::perftime, 423
decrement_current	seq64::seqevent, 476
seq64::eventslots, 157	draw_background_on
decrement_data1	seq64::perfroll, 413
	draw_background_on_pixmap
seq64::event, 122	seq64::seqroll, 505
decrement_data2	draw_drawable
seq64::event, 122 decrement_offset	
	seq64::gui_drawingarea_gtk2, 185
seq64::trigger, 570	draw_drawable_row
decrement_screenset	seq64::perfroll, 413
seq64::perform, 390	draw_event
decrement_selected	seq64::eventslots, 155
seq64::sequence, 556	draw_events
decrement_tick_end	seq64::eventslots, 155
seq64::trigger, 570	draw_events_on
decrement_tick_start	seq64::seqdata, 449
seq64::trigger, 570	seq64::seqevent, 477
decrement_top	seq64::seqroll, 509
seq64::eventslots, 156	draw_events_on_pixmap
deinit	seq64::seqdata, 450
seq64::jack_assistant, 203	seq64::seqevent, 476
deinit_in	seq64::seqroll, 505
seq64::midibus, 309	draw_key
deinit_jack	seq64::seqkeys, 487
seq64::perform, 393	draw_line
del_selected_trigger	seq64::gui_drawingarea_gtk2, 180-182
seq64::sequence, 545	draw_line_on_pixmap
del_trigger	seq64::gui_drawingarea_gtk2, 181
seq64::sequence, 543	draw_line_on_window
delete_current_event	seq64::seqdata, 449
seq64::eventslots, 152	draw_marker_on_sequence
delete_current_sequence	seq64::mainwid, 253
seq64::seqmenu, 494	draw_normal_rectangle_on_pixmap
delete_lash_driver	seq64::gui_drawingarea_gtk2, 185
seq64, 72	draw_pixmap_on_window
delete_sequence	seq64::mainwid, 253
seq64::perform, 371	seq64::perftime, 425
delta_time_us_to_ticks	seq64::seqdata, 450
seq64, 62	seq64::seqevent, 476
device_ignore	seq64::seqtime, 522
seq64::rc_settings, 433, 434	draw_progress
device_ignore_num	seq64::perfroll, 412
seq64::rc_settings, 433, 434	draw_progress_on_window
divisions	seq64::perftime, 423
seq64::midi_measures, 296	seq64::seqroll, 506
	sequ4seqioli, 500
do_action	seq64::seqtime, 522
do_action seq64::seqedit, 466	·

draw_rectangle_on_pixmap	seq64::options, 332
seq64::gui_drawingarea_gtk2, 185	e_jack_master
draw_selection_on_window	seq64::options, 332
seq64::seqevent, 476	e_jack_master_cond
seq64::seqroll, 505	seq64::options, 332
draw_sequence	e_jack_start_mode_live
seq64::perfnames, 351	seq64::options, 332
draw_sequence_on	e_jack_start_mode_song
seq64::perfroll, 413	seq64::options, 332
draw_sequence_on_pixmap	e_jack_transport
seq64::mainwid, 254	seq64::options, 332
draw_sequence_pixmap_on_window	e_number_of_interactions
seq64::mainwid, 254	seq64, <mark>53</mark>
draw_sequences	e_remove_one
seq64::perfedit, 344	seq64::sequence, 533
seq64::perfnames, 351	e_select
draw_sequences_on_pixmap	seq64::sequence, 533
seq64::mainwid, 254	e_select_one
draw_type_t	seq64::sequence, 533
seq64, 54	e_seq24_interaction
dref	seq64, 53
seq64::editable_events, 109	e_toggle_selection
seq64::event_list, 132	seq64::sequence, 533
drop_action	e_would_select
seq64::seqroll, 513	seq64::sequence, 533
drop_event	EVENT_AFTERTOUCH
seq64::seqevent, 477	seq64, 76
drop_x	EVENT ANY
seq64::gui_drawingarea_gtk2, 180	seq64, 75
drop_y	EVENT_CHANNEL_PRESSURE
seq64::gui_drawingarea_gtk2, 180	seq64, 76
dump_midi_input	EVENT_CLEAR_CHAN_MASK
seq64::mastermidibus, 279	seq64, 77
dump_setting_summary	EVENT_CONTROL_CHANGE
seq64::userfile, 611	seq64, 76
dump_summary	EVENT_GET_CHAN_MASK
seq64::user_settings, 601	
	seq64, 77 EVENT MIDI ACTIVE SENS
e_action_draw	
seq64, 54	seq64, 77 EVENT MIDI CLOCK
e_action_grow	
seq64, 54	seq64, 76
e_action_select	EVENT_MIDI_CONTINUE
seq64, 54	seq64, 77
e_clock_mod	EVENT_MIDI_META
seq64, 53	seq64, 77
e_clock_off	EVENT_MIDI_QUARTER_FRAME
seq64, 53	seq64, 76
e_clock_pos	EVENT_MIDI_RESET
seq64, 53	seq64, 77
e_deselect	EVENT_MIDI_SONG_F4
seq64::sequence, 533	seq64, 76
e_fruity_interaction	EVENT_MIDI_SONG_F5
seq64, 53	seq64, 76
e_is_selected	EVENT_MIDI_SONG_F9
seq64::sequence, 533	seq64, 76
e_jack_connect	EVENT_MIDI_SONG_FD
seq64::options, 332	seq64, 77
e_jack_disconnect	EVENT_MIDI_SONG_POS

seq64, 76	errdump
EVENT_MIDI_SONG_SELECT	seq64::midifile, 326
seq64, 76	error_is_fatal
EVENT_MIDI_START	seq64::midifile, 317
seq64, 77	error_message
EVENT_MIDI_STOP	seq64::jack_assistant, 206
seq64, 77	seq64::midifile, 317
EVENT_MIDI_SYSEX_CONTINUE	seq64::optionsfile, 337
seq64, 76	event
EVENT_MIDI_SYSEX_END	seq64::event, 116
seq64, 76	event_count
EVENT_MIDI_SYSEX	seq64::eventslots, 151
seq64, 76	seq64::sequence, 534 event edit
EVENT_MIDI_TUNE_SELECT	seq64::keys_perform, 226
seq64, 76	event_in_range
EVENT_NOTE_OFF	seq64::sequence, 562
seq64, 75	event_key
EVENT_NOTE_ON	seq64::event_list::event_key, 126, 127
seq64, 76	event list
EVENT_NULL_CHANNEL	seq64::event_list, 130
seq64, 77	event name
EVENT_PITCH_WHEEL	seq64::editable_event::name_value_t, 330
seq64, 76 EVENT_PROGRAM_CHANGE	event value
seq64, 76	seq64::editable_event::name_value_t, 330
EVENT_STATUS_BIT	EventStack
seq64, 75	seq64::sequence, 533
EVENTS_ALL	eventedit
seq64, 77	seq64::eventedit, 139
EVENTS_UNSELECTED	seq64::eventslots, 158
seq64, 77	Events
edit_action_t	seq64::editable_events, 107
seq64, 54	seq64::event_list, 130
edit_callback_notepad	events
seq64::mainwnd, 265	seq64::editable_events, 109
editable event	seq64::event_list, 134
seq64::editable_event, 100	seq64::keybindentry, 215
editable_events	seq64::sequence, 534
seq64::editable_events, 107, 108	EventsPair
seq64::event_list, 134	seq64::editable_events, 107
empty	seq64::event_list, 130
seq64::event_list, 131	eventslots seq64::editable events, 110
end	seq64::eventedit, 144
seq64::editable_events, 109	seq64::eventslots, 151
seq64::event_list, 130	expand
enqueue_draw	seq64::perfedit, 344
seq64::eventedit, 140	seq64::perform, 374
seq64::eventslots, 155	extract_timing_numbers
seq64::perfedit, 342	seq64, 55
seq64::perfnames, 351	3343., 33
seq64::perfroll, 414	FF_RW_FORWARD
seq64::perftime, 423	seq64::perform, 367
enregister	FF_RW_NONE
seq64::perform, 369	seq64::perform, 367
enregister_peer	FF_RW_REWIND
seq64::perfedit, 343	seq64::perform, 367
enregister_perfedits	FF_RW_timeout
seq64::mainwnd, 267	seq64, 75

ff_rw_button_t	flush
seq64::perform, 366	seq64::mastermidibus, 277
fg_color	seq64::midibus, 311
seq64::gui_palette_gtk2, 193	follow_progress
file access	seq64::perfroll, 412
seq64, 67	seq64::seqroll, 507
file_accessible	font
seq64, 68	seq64::font, 161
file_executable	font_render
seq64, 68	seq64, 74
file exists	force draw
seq64, 67	seq64::gui_drawingarea_gtk2, 180
file_exit	seq64::seqevent, 477
seq64::mainwnd, 268	seq64::seqkeys, 486
	seq64::seqroll, 507
file_import_dialog	format_timestamp
seq64::mainwnd, 267	seq64::editable_event, 103
file_is_directory	FruityPerfInput
seq64, 68	seq64::FruityPerfInput, 165
file_new	seq64::perfroll, 417
seq64::mainwnd, 267	seq64::triggers, 581
file_open	FruitySeqEventInput
seq64::mainwnd, 267	seq64::FruitySeqEventInput, 168
file_readable	seq64::seqevent, 481
seq64, 67	FruitySeqRollInput
file_save	
seq64::mainwnd, 267	seq64::FruitySeqRollInput, 171
file_save_as	seq64::seqkeys, 490
seq64::mainwnd, 268	seq64::seqroll, 517
file_writable	g_rc_settings
seq64, 68	seq64, 84
filename	g_user_settings
seq64::rc_settings, 433, 435	seq64, 84
fill	GROW END
seq64::midi_container, 285	seq64::triggers, 573
fill_background_pixmap	GROW MOVE
seq64::perfroll, 411	seq64::triggers, 573
fill background window	GROW_START
seq64::mainwid, 253	seq64::triggers, 573
fill_meta_track_end	get
seq64::midi_container, 288	seq64::midi container, 286
fill_proprietary	seq64::midi_container, 200 seq64::midi_list, 295
seq64::midi_container, 288	seq64::midi_nst, 293 seq64::midi_vector, 306
fill seq name	· —
seq64::midi_container, 287	get_32nds_per_quarter
fill_seq_number	seq64::perform, 369
seq64::midi_container, 287	seq64::sequence, 537
fill_time_sig_and_tempo	get_alsa_seq
seq64::midi container, 288	seq64::mastermidibus, 276
· —	get_beat_width
fill_top_bar	seq64::jack_assistant, 202
seq64::seqedit, 464	seq64::perform, 368
filter_by_channel	seq64::sequence, 536
seq64::mastermidibus, 277	get_beats_per_bar
seq64::perform, 369	seq64::perform, 368
seq64::rc_settings, 433, 434	seq64::sequence, 536
filter_callback	get_beats_per_measure
seq64::options, 332	seq64::jack_assistant, 202
finish	get_beats_per_minute
seq64::perform, 372	seq64::jack_assistant, 202

seq64::mastermidibus, 277	seq64::event, 123
seq64::perform, 383	get_max_trigger
get_channel	seq64::perform, 374
seq64::event, 118	seq64::sequence, 546
get_client	get_maximum
seq64::midibus, 311	seq64::triggers, 578
get_clipboard_box	get_measures
seq64::sequence, 551	seq64::seqedit, 462
get_clock	seq64::sequence, 536
seq64::mastermidibus, 281	get_midi_bus
seq64::midibus, 311	seq64::sequence, 547
get_clock_mod	get_midi_channel
seq64::midibus, 311	seq64::sequence, 541
get_current_jack_position	get_midi_event
seq64::jack_assistant, 211	seq64::mastermidibus, 279
get_current_sequence	get_midi_in_bus_name
seq64::seqmenu, 494	seq64::mastermidibus, 277
get_data	get_midi_out_bus_name
seq64::event, 122	seq64::mastermidibus, 277
get_editing	get_minmax_note_events
seq64::sequence, 537	seq64::sequence, 559
get_group_mute_state	get_name
seq64::perform, 385	seq64::midibus, 310
get_hold_undo	seq64::sequence, 537
seq64::sequence, 535	get_next_event
get_id	seq64::sequence, 560
seq64::midibus, 310	get_next_note_event
get_input	seq64::sequence, 559
seq64::mastermidibus, 281	get_next_trigger
seq64::midibus, 311	seq64::sequence, 560
get_jack_client_info	get_note
seq64::jack_assistant, 207	seq64::event, 124
get_jack_pos	get_note_velocity
seq64::jack_assistant, 206	seq64::event, 124
get_jack_tick	get_num_in_buses
seq64::jack_assistant, 206	seq64::mastermidibus, 276
seq64::perform, 372	get_num_out_buses
get_key_events	seq64::mastermidibus, 276
seq64::keys_perform, 227	get_num_selected_events
seq64::perform, 386	seq64::sequence, 549
get_key_events_rev	get_num_selected_notes
seq64::keys_perform, 227	seq64::sequence, 549
seq64::perform, 386	get_offset
get_key_groups	seq64::perform, 386
seq64::keys_perform, 227	get_playing
seq64::perform, 386	seq64::sequence, 538
get_key_groups_rev	get_playing_screenset
seq64::keys_perform, 227	seq64::perform, 377
seq64::perform, 386	get_port
get_keys	seq64::midibus, 311
seq64::keys_perform, 223	get_ppqn
get_last_tick	seq64::jack_assistant, 202
seq64::sequence, 538	seq64::mastermidibus, 277
get_left_tick	seq64::sequence, 536
seq64::perform, 372	get_quantized_rec
get_length	seq64::sequence, 539
seq64::sequence, 538	get_queued
get_linked	seq64::sequence, 539

get_queued_tick	green
seq64::sequence, 539	seq64::gui_palette_gtk2, 193
get_raise	grey
seq64::sequence, 537	seq64::gui_palette_gtk2, 193
get_rank	grid_brackets
seq64::event, 125	seq64::user_settings, 599, 600
get_recording	grid_is_black
seq64::sequence, 539	seq64::user_settings, 599
get_right_tick	grid_is_normal
seq64::perform, 373	seq64::user_settings, 599
get_screen_set_notepad	grid_is_white
seq64::perform, 375	seq64::user_settings, 599
get_screenset	grid_style
seq64::perform, 376	seq64::user_settings, 598, 600
get_selected_box	grid_style_black
seq64::seqroll, 509	seq64::user_settings, 597
seq64::sequence, 551	grid_style_max
get_selected_end	seq64::user_settings, 597
seq64::triggers, 578	grid_style_normal
get_selected_start	seq64::user_settings, 597
seq64::triggers, 578	grid_style_white
get_sequence	seq64::user_settings, 597
seq64::mastermidibus, 279	group_learn
seq64::perform, 381	seq64::keys_perform, 225
seq64::seqmenu, 494	group_off
get_song_mute	seq64::keys_perform, 225
seq64::sequence, 537	group_on
get_start_tick	seq64::keys_perform, 225
seq64::perform, 372	groups
get_state	seq64::keybindentry, 215
seq64::triggers, 576	grow
get_status	seq64::perfedit, 343
seq64::event, 122	seq64::triggers, 576
get_sysex	grow_edit_t
seq64::event, 123	seq64::triggers, 573
get_sysex_size	grow_selected
seq64::event, 123	seq64::sequence, 556
get_thru	grow_selected_notes
seq64::sequence, 539	seq64::seqroll, 510
get_tick	grow_trigger
seq64::perform, 372	seq64::sequence, 543
get_timestamp	growing
seq64::event, 118	seq64::seqroll, 513
get_trigger_count	gs_mainwid_pointer
seq64::sequence, 534	seq64, 84
get_trigger_offset	gs_perfedit_pointer_0
seq64::sequence, 547	seq64, 84
get_trigger_paste_tick	gs_perfedit_pointer_1
seq64::sequence, 534	seq64, 84
seq64::triggers, 580	Gtk, 41
get_trigger_state	gtk_drawarea_init
seq64::sequence, 543	seq64::gui_drawingarea_gtk2, 186
get_triggers	gui
seq64::sequence, 543	seq64::perform, 369
global_seq_feature	gui_assistant
seq64::user_settings, 599, 600	seq64::gui_assistant, 173
gmute_tracks	gui_assistant_gtk2
seq64::user_settings, 599	seq64::gui_assistant_gtk2, 175

gui_drawingarea_gtk2	idle_redraw
seq64::gui_drawingarea_gtk2, 179	seq64::seqdata, 448
gui_palette_gtk2	seq64::seqevent, 477
seq64::gui_palette_gtk2, 192	seq64::seqroll, 509
gui_window_gtk2	in_range
seq64::gui_window_gtk2, 196	seq64::midi_control, 291
7 0 = =0 7	increment
handle_cancel	seq64::midi_splitter, 299
seq64::eventedit, 143	increment_beats_per_minute
handle close	seq64::perform, 390
seq64::eventedit, 143	increment bottom
seq64::seqedit, 466	seq64::eventslots, 157
handle_config	•
seq64::lash, 241	increment_current
handle_delete	seq64::eventslots, 157
seq64::eventedit, 143	increment_data1
handle_event	seq64::event, 122
seq64::lash, 241	increment_data2
•	seq64::event, 122
handle_insert	increment_offset
seq64::eventedit, 143	seq64::trigger, 570
handle_midi_control	increment_screenset
seq64::perform, 375	seq64::perform, 390
handle_modify	increment_selected
seq64::eventedit, 143	seq64::sequence, 555
handle_motion_key	increment size
seq64::Seq24PerfInput, 442	seq64::perfroll, 412
handle_save	seq64::perftime, 423
seq64::eventedit, 143	increment_tick_end
handle_signal	seq64::trigger, 570
seq64::mainwnd, 265	increment_tick_start
have_redo	
seq64::perform, 374	seq64::trigger, 570
seq64::sequence, 535	increment_top
have undo	seq64::eventslots, 157
seq64::perform, 374	info_message
seq64::sequence, 535	seq64::jack_assistant, 206
height	init
seq64::gui_drawingarea_gtk2::rect, 439	seq64::font, 161
seq64::rect, 439	seq64::jack_assistant, 202
help_check	seq64::lash, 240
seq64, 65	seq64::mastermidibus, 276
seq64::rc_settings, 437	init_before_show
highlight	seq64::perfedit, 342
seq64::perform, 390	seq64::perfroll, 411
home config directory	init_clock
	seq64::mastermidibus, 278
seq64::rc_settings, 436	seq64::midibus, 311
horizontal_adjust	init_in
seq64::perfroll, 414	seq64::midibus, 309
seq64::seqedit, 461	init_in_sub
seq64::seqroll, 507	
horizontal_set	seq64::midibus, 310
seq64::perfroll, 414	init_jack
seq64::seqedit, 462	seq64::perform, 393
	init_out
idle_progress	seq64::midibus, 309
seq64::maintime, 247	init_out_sub
seq64::perftime, 425	seq64::midibus, 309
seq64::seqroll, 509	initialize
seq64::seqtime, 522	seq64::midi_splitter, 299

inner_start	seq64::seqkeys, 487
seq64::perform, 396	is_channel_msg
inner stop	seq64::event, 118
seq64::perform, 397	is_control_status
input callback	seq64::perform, 368
seq64::options, 332	is_current_seq_active
input_func	seq64::seqmenu, 494
seq64::perform, 385	is_current_seq_in_edit
input_thread_func	seq64::seqmenu, 494
seq64, 73	is_delete
insert_event	seq64::keystroke, 238
seq64::eventslots, 152	is_desired_cc_or_not_cc
install_sequence	seq64::event, 120
seq64::perform, 396	is_dirty_edit
install_signal_handlers	seq64::perform, 380
seq64::mainwnd, 269	seq64::sequence, 540
instrument	is_dirty_main
seq64::user_instrument_t, 585	seq64::perform, 380
seq64::user_midi_bus, 588	seq64::sequence, 540
seq64::user_midi_bus_t, 589	is_dirty_names
seq64::user_settings, 598	seq64::perform, 380
instrument_controller_active	seq64::sequence, 540
seq64::user_settings, 598	is_dirty_perf
instrument_controller_name	seq64::perform, 380
seq64::user_settings, 598	seq64::sequence, 540
instrument_count	is_dumping
	seq64::mastermidibus, 279
seq64::user_settings, 598	•
instrument_name	is_edit_sequence
seq64::user_settings, 598 InstrumentConstIterator	seq64::perform, 368
	seq64::seqmenu, 494
seq64::user_settings, 597	is_exportable
InstrumentIterator	seq64::perform, 381
seq64::user_settings, 597	is_group_learning
Instruments	seq64::perform, 378
seq64::user_settings, 597	is_inverse
interaction_method	seq64::gui_palette_gtk2, 192
seq64::rc_settings, 433, 435	is_jack_master
interaction_method_t	seq64::perform, 369
seq64, 53	is_jack_running
intersect	seq64::perform, 369
seq64::triggers, 577	is_left
intersect_events	seq64::click, 90
seq64::sequence, 545	is_letter
intersect_notes	seq64::keystroke, 238
seq64::sequence, 544	is_linked
intersect_triggers	seq64::event, 123
seq64::sequence, 544	is_marked
inverse_active	seq64::event, 124
seq64::midi_control, 291	is_master
inverse_colors	seq64::jack_assistant, 201
seq64::user_settings, 600, 602	is_middle
is	seq64::click, 90
seq64::keystroke, 238	is_midi_control_valid
is_active	seq64::perform, 393
seq64::perform, 381	is_modified
is_adding	seq64::event_list, 131
seq64::Seq24PerfInput, 442	seq64::perform, 367, 393
is_black_key	seq64::seqmenu, 494

is_more_input	seq64::event_list, 130
seq64::mastermidibus, 278	jack_assistant
is_mseq_valid	• —
seq64::perform, 396	seq64::jack_assistant, 201
is_note	seq64::perform, 398
seq64::event, 124	jack_idle_connect
is_note_msg	seq64::gui_assistant, 173
seq64::event, 119	seq64::gui_assistant_gtk2, 175
is_note_off	jack_process_callback
seq64::event, 124	seq64, 71
is_note_off_recorded	seq64::jack_assistant, 210
seq64::event, 125	jack_session_callback
is_note_on	seq64, 71
seq64::event, 124	seq64::jack_assistant, 211
is_one_byte_msg	jack_session_uuid
seq64::event, 118	seq64::rc_settings, 433, 435
is_painted	jack_shutdown_callback
seq64::event, 123	seq64, 70
is_pattern_playing	seq64::jack_assistant, 210
	jack_sync_callback
seq64::perform, 369, 394	seq64, 69
is_pausable	seq64::jack_assistant, 210
seq64::perform, 369	seq64::perform, 398
is_paused	jack_timebase_callback
seq64::perform, 369	seq64, 70
is_press	seq64:;ack_assistant, 210
seq64::click, 90	jf_bit
seq64::keystroke, 238	seq64::jack_status_pair_t, 214
is_realized	jf_meaning
seq64::gui_window_gtk2, 197	seq64::jack_status_pair_t, 214
is_right	js_clock_tick
seq64::click, 90	• — —
is_running	seq64::jack_scratchpad, 214
seq64::jack_assistant, 201	js_current_tick
seq64::perform, 369	seq64::jack_scratchpad, 214
is_save	js_dumping
seq64::mainwnd, 269	seq64::jack_scratchpad, 214
is screenset valid	js_init_clock
seq64::perform, 394	seq64::jack_scratchpad, 214
is selected	js_jack_stopped
seq64::event, 124	seq64::jack_scratchpad, 214
is_seq_valid	js_looping
seq64::perform, 394	seq64::jack_scratchpad, 214
is_sequence_in_edit	js_playback_mode
seq64::perform, 371	seq64::jack_scratchpad, 214
• •	js_ticks_converted_last
is_smf_0	seq64::jack_scratchpad, 214
seq64::perform, 390	js_total_tick
seq64::sequence, 541	seq64::jack_scratchpad, 214
is_strict_note_msg	
seq64::event, 119	keep_queue
is_sysex_special_id	seq64::keys_perform, 223, 224
seq64::midifile, 327	Key
is_two_byte_msg	seq64::editable_events, 107
seq64::event, 119	key
is_valid	seq64::keystroke, 238
seq64::user_instrument, 583	key_name
seq64::user_midi_bus, 587	seq64::keys_perform, 227
iterator	seq64::keys_perform_gtk2, 234
seq64::editable_events, 107	seq64::perform, 386

kov progo ovont	look
key_press_event	lash
seq64::perftime, 426	seq64::lash, 240
keybindentry	lash_driver
seq64::keybindentry, 215	seq64, 72
seq64::perform, 398	lash_support
keys	seq64::rc_settings, 432, 434
seq64::gui_assistant, 174	lash_support_callback
seq64::perform, 369	seq64::options, 333
keys_perform	lash_timeout_connect
seq64::keys_perform, 222	seq64::gui_assistant, 173
keys_perform_gtk2	seq64::gui_assistant_gtk2, 175
seq64::keys perform gtk2, 234	last_used_dir
keystroke	seq64::rc_settings, 433, 435
seq64::keystroke, 237	launch
keyval_name	seq64::perform, 370
seq64, 71	launch_input_thread
keyval normalize	seq64::perform, 392
seq64, 72	launch_output_thread
•	_ · _
kpt_bpm_dn	seq64::perform, 393
seq64::keys_perform_transfer, 235	learn_toggle
kpt_bpm_up	seq64::mainwnd, 266
seq64::keys_perform_transfer, 235	seq64::perform, 389
kpt_event_edit	left_right_size
seq64::keys_perform_transfer, 236	seq64::perform, 373
kpt_group_learn	legacy_format
seq64::keys_perform_transfer, 235	seq64::rc_settings, 432, 434
kpt_group_off	length
seq64::keys_perform_transfer, 235	seq64::trigger, 570
kpt_group_on	lfownd
seq64::keys_perform_transfer, 235	seq64::lfownd, 243
kpt_keep_queue	seq64::seqdata, 452
seq64::keys_perform_transfer, 235	light_grey
kpt pattern edit	seq64::gui_palette_gtk2, 193
seq64::keys_perform_transfer, 236	line_after
kpt_pause	seq64::configfile, 94
seq64::keys_perform_transfer, 236	line_color
kpt_queue	seq64::gui_palette_gtk2, 192
seq64::keys_perform_transfer, 235	line count
kpt_replace	seq64::eventslots, 151
seq64::keys_perform_transfer, 235	line_increment
	seq64::eventslots, 151
kpt_screenset_dn	
seq64::keys_perform_transfer, 235	line_maximum
kpt_screenset_up	seq64::eventslots, 151
seq64::keys_perform_transfer, 235	link
kpt_set_playing_screenset	seq64::event, 123
seq64::keys_perform_transfer, 235	link_new
kpt_show_ui_sequence_key	seq64::event_list, 132
seq64::keys_perform_transfer, 236	seq64::sequence, 558
kpt_show_ui_sequence_number	List
seq64::keys_perform_transfer, 236	seq64::triggers, 573
kpt_snapshot_1	load_events
seq64::keys_perform_transfer, 235	seq64::editable_events, 108
kpt_snapshot_2	seq64::eventslots, 151
seq64::keys_perform_transfer, 235	load_inverse_palette
kpt_start	seq64::gui_palette_gtk2, 192
seq64::keys_perform_transfer, 236	location
kpt_stop	seq64::keybindentry, 215
seq64::keys_perform_transfer, 236	lock
· · · · · · · · · · · · · · · · · · ·	

seq64::mutex, 330	m_background_x
log2_time_sig_value	seq64::perfroll, 418
seq64, 60	m_bar_width
log_main_sequence	seq64::maintime, 247
seq64::midi_splitter, 298	m_beat_length
long_options	seq64::perfroll, 418
seq64, 82	m_beat_width
lookup_keyevent_key	seq64::jack_assistant, 213
seq64::keys_perform, 227	seq64::maintime, 247
seq64::perform, 387	seq64::midi_timing, 303
lookup_keyevent_seq	seq64::perform, 401
seq64::keys_perform, 227	m_beats
seq64::perform, 387	seq64::midi_measures, 297
lookup_keygroup_group	m_beats_per_bar
seq64::keys_perform, 227	seq64::perform, 401
seq64::perform, 388	m_beats_per_measure
lookup_keygroup_key	seq64::jack_assistant, 213
seq64::keys_perform, 227	seq64::midi_timing, 303
seq64::perform, 387	m_beats_per_minute
	seq64::jack_assistant, 213
m_32nds_per_quarter	seq64::mastermidibus, 282
seq64::perform, 402	seq64::midi_timing, 302
seq64::sequence, 567	m_bg_color
m_4bar_offset	seq64::gui palette gtk2, 194
seq64::perfroll, 418	m_bgsequence
seq64::perftime, 426	seq64::seqedit, 468
m_active	m_black
seq64::midi_control, 291	seq64::gui_palette_gtk2, 193
m_adding	m_black_pixmap
seq64::Seq24PerfInput, 442	seq64::font, 162
seq64::Seq24SeqEventInput, 444	m_blk_key
seq64::seqroll, 518	seq64::gui_palette_gtk2, 194
m_adding_pressed	m_blk_paint
seq64::AbstractPerfInput, 86	seq64::gui_palette_gtk2, 194
m_adjust_bpm	m_blue
seq64::mainwnd, 271	seq64::gui_palette_gtk2, 194
m_adjust_load_offset	m_bottbox
seq64::mainwnd, 271	seq64::eventedit, 145
m_adjust_ss	m_bottom_iterator
seq64::mainwnd, 271	seq64::eventslots, 159
m_allow_mod4_mode	m box height
seq64::rc_settings, 437	seq64::maintime, 248
m_allow_snap_split	m_box_less_pill
seq64::rc_settings, 437	seq64::maintime, 248
m_allow_two_perfedits	m_box_width
seq64::user_settings, 606	seq64::maintime, 248
m_alsa_seq	•
seq64::mastermidibus, 281	m_bpm seq64::perfedit, 347
m_auto_option_save	m bus
seq64::rc_settings, 437	_
m_b_on_c_pixmap	seq64::sequence, 565
seq64::font, 163	m_bus_announce
m_b_on_y_pixmap	seq64::mastermidibus, 282
seq64::font, 163	m_buses_in
m_background	seq64::mastermidibus, 282
seq64::gui_drawingarea_gtk2, 187	m_buses_in_active
m_background_sequence	seq64::mastermidibus, 282
seq64::seqroll, 519	m_buses_in_init
seq64::sequence, 568	seq64::mastermidibus, 282

m_buses_out	m_button_ok
seq64::mastermidibus, 281	seq64::options, 333
m_buses_out_active	m_button_perfedit
seq64::mastermidibus, 282	seq64::mainwnd, 271
m_buses_out_init	m_button_play
seq64::mastermidibus, 282	seq64::mainwnd, 271
m_button	seq64::perfedit, 346
seq64::click, 90	m_button_quantize
m_button_bpm	seq64::seqedit, 470
seq64::perfedit, 347	m_button_rec_vol
seq64::seqedit, 471	seq64::seqedit, 471
m_button_bus	m_button_redo
seq64::seqedit, 470	seq64::perfedit, 347
m_button_bw	seq64::seqedit, 470
seq64::perfedit, 347	m_button_save
seq64::seqedit, 471	seq64::eventedit, 145
m_button_cancel	m_button_scale
seq64::eventedit, 145	seq64::seqedit, 471
m_button_channel	m_button_sequence
seq64::seqedit, 470	seq64::seqedit, 470
m_button_collapse	m_button_snap
seq64::perfedit, 347	seq64::perfedit, 346
·	seq64::seqedit, 470
m_button_copy	
seq64::perfedit, 347	m_button_stop
m_button_data	seq64::mainwnd, 271
seq64::seqedit, 471	seq64::perfedit, 346
m_button_del	m_button_tools
seq64::eventedit, 145	seq64::seqedit, 470
m_button_down	m_button_undo
seq64::mainwid, 258	seq64::perfedit, 347
m_button_expand	seq64::seqedit, 470
seq64::perfedit, 347	m_button_zoom
m_button_grow	seq64::seqedit, 471
seq64::perfedit, 347	m_bw
m_button_ins	seq64::perfedit, 347
seq64::eventedit, 145	m_c_on_b_pixmap
m_button_jack_connect	seq64::font, 163
seq64::options, 333	m_call_seq_edit
m_button_jack_disconnect	seq64::mainwnd, 272
seq64::options, 333	m_call_seq_eventedit
m_button_jack_master	seq64::mainwnd, 272
seq64::options, 333	m_category
	04 111 1 10 5
m_button_jack_master_cond	seq64::editable_event, 105
m_button_jack_master_cond seq64::options, 333	seq64::editable_event, 105 m_cc
	•
seq64::options, 333	m_cc
seq64::options, 333 m_button_jack_transport	m_cc seq64::seqdata, 453
seq64::options, 333 m_button_jack_transport seq64::options, 333	m_cc seq64::seqdata, 453 seq64::seqevent, 482
seq64::options, 333 m_button_jack_transport seq64::options, 333 m_button_key	m_cc seq64::seqdata, 453 seq64::seqevent, 482 seq64::seqroll, 519
seq64::options, 333 m_button_jack_transport seq64::options, 333 m_button_key seq64::seqedit, 471 m_button_learn	m_cc seq64::seqdata, 453 seq64::seqevent, 482 seq64::seqroll, 519 m_cell_h
seq64::options, 333 m_button_jack_transport seq64::options, 333 m_button_key seq64::seqedit, 471 m_button_learn seq64::mainwnd, 271	m_cc seq64::seqdata, 453 seq64::seqevent, 482 seq64::seqroll, 519 m_cell_h seq64::font, 162 m_cell_w
seq64::options, 333 m_button_jack_transport seq64::options, 333 m_button_key seq64::seqedit, 471 m_button_learn seq64::mainwnd, 271 m_button_length	m_cc seq64::seqdata, 453 seq64::seqevent, 482 seq64::seqroll, 519 m_cell_h seq64::font, 162 m_cell_w seq64::font, 162
seq64::options, 333 m_button_jack_transport seq64::options, 333 m_button_key seq64::seqedit, 471 m_button_learn seq64::mainwnd, 271 m_button_length seq64::seqedit, 471	m_cc seq64::seqdata, 453 seq64::seqevent, 482 seq64::seqroll, 519 m_cell_h seq64::font, 162 m_cell_w seq64::font, 162 m_channel
seq64::options, 333 m_button_jack_transport seq64::options, 333 m_button_key seq64::seqedit, 471 m_button_learn seq64::mainwnd, 271 m_button_length seq64::seqedit, 471 m_button_loop	m_cc seq64::seqdata, 453 seq64::seqevent, 482 seq64::seqroll, 519 m_cell_h seq64::font, 162 m_cell_w seq64::font, 162 m_channel seq64::event, 125
seq64::options, 333 m_button_jack_transport seq64::options, 333 m_button_key seq64::seqedit, 471 m_button_learn seq64::mainwnd, 271 m_button_length seq64::seqedit, 471 m_button_loop seq64::perfedit, 346	m_cc seq64::seqdata, 453 seq64::seqevent, 482 seq64::seqroll, 519 m_cell_h seq64::font, 162 m_cell_w seq64::font, 162 m_channel seq64::event, 125 m_channel_count
seq64::options, 333 m_button_jack_transport seq64::options, 333 m_button_key seq64::seqedit, 471 m_button_learn seq64::mainwnd, 271 m_button_length seq64::seqedit, 471 m_button_loop seq64::perfedit, 346 m_button_modify	m_cc seq64::seqdata, 453 seq64::seqevent, 482 seq64::seqroll, 519 m_cell_h seq64::font, 162 m_cell_w seq64::font, 162 m_channel seq64::event, 125 m_channel_count seq64::user_midi_bus, 589
seq64::options, 333 m_button_jack_transport seq64::options, 333 m_button_key seq64::seqedit, 471 m_button_learn seq64::mainwnd, 271 m_button_length seq64::seqedit, 471 m_button_loop seq64::perfedit, 346 m_button_modify seq64::eventedit, 145	m_cc seq64::seqdata, 453 seq64::seqevent, 482 seq64::seqroll, 519 m_cell_h seq64::font, 162 m_cell_w seq64::font, 162 m_channel seq64::event, 125 m_channel_count seq64::user_midi_bus, 589 m_channel_match
seq64::options, 333 m_button_jack_transport seq64::options, 333 m_button_key seq64::seqedit, 471 m_button_learn seq64::mainwnd, 271 m_button_length seq64::seqedit, 471 m_button_loop seq64::perfedit, 346 m_button_modify	m_cc seq64::seqdata, 453 seq64::seqevent, 482 seq64::seqroll, 519 m_cell_h seq64::font, 162 m_cell_w seq64::font, 162 m_channel seq64::event, 125 m_channel_count seq64::user_midi_bus, 589

seq64::midi_list, 295	seq64::midifile, 328
seq64::midifile, 328	m_dest_addr_client
m_char_vector	seq64::midibus, 312
seq64::midi_vector, 306	m_dest_addr_port
m char w	seq64::midibus, 312
seq64::eventslots, 158	m_device_ignore
seq64::perfnames, 354	seq64::rc_settings, 438
m_client	m_device_ignore_num
seq64::lash, 241	seq64::rc_settings, 438
m_clip_mask	m_dirty_edit
seq64::font, 163	seq64::sequence, 566
m clipboard	m_dirty_main
seq64::seqmenu, 497	seq64::sequence, 566
seq64::triggers, 581	m_dirty_names
m_clock_mod	seq64::sequence, 566
seq64::midibus, 312	m_dirty_perf
m_clock_type	seq64::sequence, 566
seq64::midibus, 312	m disable reported
m_clocks_per_metronome	seq64::midifile, 327
seq64::perform, 401	m_divisions
seq64::sequence, 567	seq64::midi_measures, 297
m_cond	m_divs_per_beat
seq64::condition_var, 92	seq64::perfroll, 417
m_condition_var	m_dk_blue
seq64::perform, 404	seq64::gui_palette_gtk2, 194
m_config_directory	m_dk_cyan
seq64::rc_settings, 438	seq64::gui_palette_gtk2, 194
m_config_filename	m_dk_green
seq64::rc_settings, 438	seq64::gui_palette_gtk2, 194
m_config_filename_alt	m_dk_grey
seq64::rc_settings, 438	seq64::gui_palette_gtk2, 194
m_control_height	m_dk_magenta
seq64::user_settings, 605	seq64::gui_palette_gtk2, 194
m_control_status	m_dk_orange
seq64::perform, 403	seq64::gui_palette_gtk2, 194
m_controller_count	m_dk_red
seq64::user_instrument, 585	seq64::gui_palette_gtk2, 194
m_current_event	m_drag_paste_start_pos
seq64::editable_events, 110	seq64::FruitySeqRollInput, 172
m_current_index	m_dragging
seq64::eventslots, 159	seq64::seqdata, 453
m_current_iterator	m_drawing_background_seq
seq64::eventslots, 159	seq64::seqroll, 519
m_current_seq	m_drop_sequence
seq64::seqmenu, 497	seq64::perfroll, 419
m_current_x	m_drop_tick
seq64::FruityPerfInput, 167	seq64::perfroll, 418
seq64::gui_drawingarea_gtk2, 187	m_drop_tick_trigger_offset
m_current_y	seq64::perfroll, 418
seq64::FruityPerfInput, 167	m_drop_x
seq64::gui_drawingarea_gtk2, 187	seq64::gui_drawingarea_gtk2, 187
m_current_zoom	m_drop_y
seq64::user_settings, 605	seq64::gui_drawingarea_gtk2, 187
m_d	m_dumping_input
seq64::configfile, 95	seq64::mastermidibus, 282
m_data	m_edit_sequence
seq64::event, 125	seq64::perform, 404
seq64::midi_control, 292	m_editbox

seq64::eventedit, 145	m_eventedit
m_editing	seq64::seqmenu, 497
seq64::sequence, 566	m_events
m_editing_cc	seq64::editable_events, 110
seq64::seqedit, 471	seq64::event_list, 135
m_editing_status	seq64::sequence, 564
seq64::seqedit, 471	m_events_clipboard
m_effective_tick	seq64::sequence, 564
seq64::Seq24PerfInput, 442	m_events_redo
m_entry_bpm	seq64::sequence, 565
seq64::perfedit, 347	m_events_undo
seq64::seqedit, 471	seq64::sequence, 565
m_entry_bus	m_events_undo_hold
seq64::seqedit, 470	seq64::sequence, 565
m_entry_bw	m_eventslots
seq64::perfedit, 347	seq64::eventedit, 145
seq64::seqedit, 471	m_fg_color
m_entry_channel	seq64::gui_palette_gtk2, 194
seq64::seqedit, 470	m_file_size
m_entry_data	seq64::midifile, 327
seq64::seqedit, 471	m filename
m_entry_ev_data_0	seq64::rc_settings, 438
seq64::eventedit, 146	m_filter_by_channel
m_entry_ev_data_1	seq64::mastermidibus, 282
seq64::eventedit, 146	seq64::rc_settings, 438
m_entry_ev_name	m_flash_height
seq64::eventedit, 146	seq64::maintime, 248
m_entry_ev_timestamp	m_flash_width
seq64::eventedit, 145	seq64::maintime, 248
m_entry_key	m_flash_x
seq64::seqedit, 471	seq64::maintime, 248
m_entry_length	m_font_h
seq64::seqedit, 471	seq64::font, 162
• •	•
m_entry_name	m_font_w
seq64::seqedit, 471	seq64::font, 162
m_entry_note_length	m_foreground
seq64::seqedit, 470	seq64::gui_drawingarea_gtk2, 187
m_entry_notes	m_format_timestamp
seq64::mainwnd, 271	seq64::editable_event, 105
m_entry_scale	m_fruity_interaction
seq64::seqedit, 471	seq64::perfroll, 419
m_entry_sequence	seq64::seqevent, 481
seq64::seqedit, 470	seq64::seqroll, 517
m_entry_snap	m_gc
seq64::perfedit, 346	seq64::gui_drawingarea_gtk2, 186
seq64::seqedit, 470	m_global_bgsequence
m_entry_zoom	seq64::midifile, 328
seq64::seqedit, 471	m_global_seq_feature_save
m_erase_painting	seq64::user_settings, 605
seq64::FruitySeqRollInput, 172	m_gmute_tracks
m_error_is_fatal	seq64::user_settings, 608
seq64::midifile, 327	m_green
m_error_message	seq64::gui_palette_gtk2, 194
seq64::midifile, 327	m_grey
m_event_container	seq64::gui_palette_gtk2, 194
seq64::eventslots, 158	m_grid_brackets
m_event_count	seq64::user_settings, 604
seq64::eventslots, 159	m_grid_style
·	

seq64::user_settings, 603	seq64::perform, 401
m_grow_direction	m_init_clock
seq64::perfroll, 419	seq64::mastermidibus, 282
m_growing	m_init_input
seq64::perfroll, 419	seq64::mastermidibus, 282
seq64::seqevent, 482	m_initial_note_length
seq64::seqroll, 518	seq64::seqedit, 468
m_gui_support	m_initial_snap
seq64::perform, 399	seq64::seqedit, 468
m_h_page_increment	m_initial_zoom
seq64::perfroll, 417	seq64::seqedit, 468
m_h_perf_page_increment	m_inputing
seq64::user_settings, 606	seq64::midibus, 312
m_hadjust	seq64::perform, 401
seq64::gui_drawingarea_gtk2, 187	m_instrument_def
seq64::perfedit, 346	seq64::user_instrument, 585
seq64::seqedit, 469	m_instruments
m_has_link	seq64::user_settings, 603
seq64::event, 126	m_interaction_method
m_have_button_press	seq64::rc_settings, 438
seq64::perfroll, 418	m_inverse_active
m_have_focus	seq64::midi_control, 291
seq64::eventedit, 146	m_inverse_colors
seq64::seqedit, 472	seq64::user_settings, 606
m_have_redo	m_is_drag_pasting
seq64::perform, 404	seq64::FruitySeqEventInput, 170
seq64::sequence, 565	seq64::seqroll, 518
m_have_undo	m_is_drag_pasting_start
seq64::perform, 404	seq64::FruitySeqEventInput, 170
seq64::sequence, 565	seq64::seqroll, 518
m_hbox	m_is_inverse
seq64::lfownd, 244	seq64::gui_palette_gtk2, 193
seq64::perfedit, 347	m_is_lash_supported
seq64::seqedit, 470	seq64::lash, 241
m_hbox2	m_is_modified
seq64::seqedit, 470	seq64::event_list, 135
m_hint_key	seq64::perform, 404
seq64::seqkeys, 490	m_is_pattern_playing
m_hint_state	seq64::perform, 401
seq64::seqkeys, 490	m_is_paused
m_hlbox	seq64::perform, 403
seq64::perfedit, 347	m_is_press
m_horizontal_adjust	seq64::click, 90
seq64::seqroll, 517	seq64::keystroke, 239
m_hscroll	m_is_realized
seq64::perfedit, 346	seq64::gui_window_gtk2, 198
m_hscroll_new	m_is_running
seq64::seqedit, 469	seq64::mainwnd, 271
m_htopbox	seq64::perfedit, 348
seq64::eventedit, 145	m_is_valid
m_id	seq64::user_instrument, 585
seq64::midibus, 312	seq64::user_midi_bus, 588
m_image_play	m_iterator_draw
seq64::mainwnd, 271	seq64::sequence, 565
seq64::perfedit, 346	m_iterator_draw_trigger
m_in_thread	seq64::triggers, 581
seq64::perform, 400	m_iterator_play_trigger
m_in_thread_launched	seq64::triggers, 581

m_jack_asst	m_key_groups_rev
seq64::perform, 404	seq64::keys_perform, 231
m_jack_client	m_key_keep_queue
seq64::jack_assistant, 212	seq64::keys_perform, 231
m_jack_client_name	m_key_pattern_edit
seq64::jack_assistant, 212	seq64::keys_perform, 232
m_jack_client_uuid	m_key_pause
seq64::jack_assistant, 212	seq64::keys_perform, 232
m_jack_frame_current	m_key_queue
seq64::jack_assistant, 212	seq64::keys_perform, 231
m_jack_frame_last	m_key_replace
seq64::jack_assistant, 212	seq64::keys_perform, 231
m_jack_master	m_key_screenset_dn
seq64::jack_assistant, 213	seq64::keys_perform, 231
m_jack_parent	m_key_screenset_up
seq64::jack_assistant, 212	seq64::keys_perform, 231
m_jack_pos	m_key_set_playing_screenset
seq64::jack_assistant, 212	seq64::keys_perform, 231
m_jack_running	m_key_show_ui_sequence_key seq64::keys_perform, 230
seq64::jack_assistant, 212 m jack session uuid	
seq64::rc_settings, 438	m_key_show_ui_sequence_number seq64::keys_perform, 230
m_jack_tick	m_key_snapshot_1
seq64::jack_assistant, 212	seq64::keys_perform, 231
seq64::jack_assistant, 212 seq64::perform, 402	m_key_snapshot_2
m_jack_transport_state	seq64::keys_perform, 231
seq64::jack_assistant, 212	m_key_start
m_jack_transport_state_last	seq64::keys_perform, 232
seq64::jack_assistant, 212	m_key_stop
m_jsession_ev	seq64::keys_perform, 232
seq64::jack_assistant, 212	m_keying
m_justselected_one	seq64::seqkeys, 490
seq64::FruitySeqEventInput, 170	m_keying_note
seq64::seqroll, 518	seq64::seqkeys, 490
m_key	m_keys_perform
seq64::keybindentry, 216	seq64::gui_assistant, 174
seq64::keystroke, 239	m_label_category
seq64::seqedit, 468	seq64::eventedit, 145
seq64::seqkeys, 490	m_label_channel
seq64::seqroll, 518	seq64::eventedit, 145
m_key_bpm_dn	m_label_ev_count
seq64::keys_perform, 231	seq64::eventedit, 145
m_key_bpm_up	m_label_modified
seq64::keys_perform, 231	seq64::eventedit, 145
m_key_event_edit	m_label_ppqn
seq64::keys_perform, 232	seq64::eventedit, 145
m_key_events	m_label_right
seq64::keys_perform, 230	seq64::eventedit, 146
m_key_events_rev	m_label_seq_name
seq64::keys_perform, 231	seq64::eventedit, 145
m_key_group_learn	m_label_spacer
seq64::keys_perform, 232	seq64::eventedit, 145
m_key_group_off	m_label_time_fmt
seq64::keys_perform, 231	seq64::eventedit, 146
m_key_group_on	m_label_time_sig
seq64::keys_perform, 231	seq64::eventedit, 145
m_key_groups	m_lash_args
seq64::keys_perform, 231	seq64::lash, 241

m_lash_support	seq64::user_settings, 609
seq64::rc_settings, 437	m_mainwid_y
m_last_tick	seq64::mainwid, 258
seq64::sequence, 566	seq64::user_settings, 609
m_last_tick_x	m_mainwnd_cols
seq64::mainwid, 258	seq64::mainwid, 258
m_last_used_dir	seq64::user_settings, 604
seq64::rc_settings, 438	m_mainwnd_rows
m lasttick	seq64::mainwid, 258
seq64::midibus, 312	seq64::user_settings, 604
m_left_marker_tick	m_manual_alsa_ports
seq64::perftime, 427	seq64::rc settings, 438
m_left_tick	m_marked
seq64::perform, 402	seq64::event, 126
m_legacy_format	m_master_bus
seq64::rc_settings, 437	seq64::perform, 400
m length	m masterbus
seq64::sequence, 567	seq64::sequence, 565
seq64::triggers, 582	m_max_busses
m_line	seq64::mastermidibus, 281
seq64::configfile, 95	•
	m_max_sequence
m_line_color	seq64::user_settings, 608
seq64::gui_palette_gtk2, 194	m_max_sets
m_line_count	seq64::mainwid, 258
seq64::eventslots, 159	seq64::perform, 403
m_line_maximum	seq64::user_settings, 604
seq64::eventslots, 159	m_max_value
m_line_overlap	seq64::midi_control, 292
seq64::eventslots, 159	m_maxbeats
m_linked	seq64::sequence, 566
seq64::event, 126	m_measure_length
m_local_addr_client	seq64::perfroll, 418
seq64::midibus, 312	seq64::perftime, 427
m_local_addr_port	m_measures
seq64::midibus, 312	seq64::midi_measures, 297
m_looping	seq64::seqedit, 468
seq64::perform, 401	m_menu
m_lt_grey	seq64::seqmenu, 497
seq64::gui_palette_gtk2, 194	m_menu_bpm
m_main_cursor	seq64::perfedit, 347
seq64::mainwnd, 271	seq64::seqedit, 469
m_main_time	m_menu_bw
seq64::mainwnd, 270	seq64::perfedit, 347
m_main_wid	seq64::seqedit, 469
seq64::mainwnd, 270	m_menu_data
m_mainperf	seq64::seqedit, 469
seq64::gui_drawingarea_gtk2, 187	m_menu_edit
seq64::gui_window_gtk2, 198	seq64::mainwnd, 270
seq64::options, 333	m_menu_file
seq64::seqmenu, 497	seq64::mainwnd, 270
m_mainwid_border	m_menu_help
seq64::mainwid, 258	seq64::mainwnd, 270
seq64::user_settings, 604	m_menu_key
m_mainwid_spacing	seq64::seqedit, 469
seq64::mainwid, 258	m_menu_length
seq64::user_settings, 604	seq64::seqedit, 469
m mainwid x	m_menu_midibus
seq64::mainwid, 258	seq64::seqedit, 469
·	•

m_menu_midich	m_mode_group_learn
seq64::seqedit, 469	seq64::perform, 399
m_menu_mode	m_modified
seq64::mainwnd, 272	seq64::seqmenu, 497
m_menu_note_length	m_modifier
seq64::seqedit, 469	seq64::click, 90
m_menu_rec_vol	seq64::keystroke, 239
seq64::seqedit, 469	m_move_delta_x
m_menu_scale	seq64::seqroll, 518
seq64::seqedit, 469	m_move_delta_y
m_menu_sequences	seq64::seqroll, 519
seq64::seqedit, 469	m_move_snap_offset_x
m_menu_snap	seq64::seqevent, 482
seq64::perfedit, 346	seq64::seqroll, 519
seq64::seqedit, 469	m_moving
m_menu_tools	seq64::mainwid, 258
seq64::seqedit, 468	seq64::perfroll, 419
·	
m_menu_view	seq64::seqevent, 482
seq64::mainwnd, 270	seq64::seqroll, 518
m_menu_zoom	m_moving_init
seq64::seqedit, 469	seq64::seqevent, 482
m_menubar	seq64::seqroll, 518
seq64::mainwnd, 270	m_moving_seq
seq64::seqedit, 468	seq64::mainwid, 258
m_midi_beat_width	m_musical_key
seq64::user_settings, 607	seq64::sequence, 568
m_midi_beats_per_measure	m_musical_scale
seq64::user_settings, 607	seq64::sequence, 568
m_midi_beats_per_minute	m_mute_group
seq64::user_settings, 607	seq64::perform, 399
m_midi_bus_def	m_mute_group_selected
seq64::user_midi_bus, 589	seq64::perform, 399
m midi buses	m mutex
seq64::user_settings, 603	seq64::mastermidibus, 282
m_midi_buss_override	seq64::midibus, 312
seq64::user settings, 608	seq64::midifile, 327
	•
m_midi_cc_off	seq64::sequence, 568
seq64::perform, 403	m_mutex_lock
m_midi_cc_on	seq64::mutex, 330
seq64::perform, 403	m_name
m_midi_cc_toggle	seq64::configfile, 95
seq64::perform, 403	seq64::midibus, 312
m_midi_channel	seq64::midifile, 328
seq64::sequence, 565	seq64::sequence, 566
m_midi_parameters	m_name_category
seq64::editable_events, 111	seq64::editable_event, 105
m_midi_ppqn	m_name_channel
seq64::user_settings, 607	seq64::editable_event, 105
m_midiclockpos	m_name_data
seq64::perform, 403	seq64::editable_event, 105
m_midiclockrunning	m_name_meta
seq64::perform, 403	seq64::editable_event, 105
m midiclocktick	m_name_seqspec
-	
seq64::perform, 403	seq64::editable_event, 105
m_min_value	m_name_status
seq64::midi_control, 292	seq64::editable_event, 105
m_mode_group	m_name_timestamp
seq64::perform, 399	seq64::editable_event, 105

m_namebox_w	m_orange
seq64::perfnames, 355	seq64::gui_palette_gtk2, 194
m_names_chars	m_out_thread
seq64::perfnames, 354	seq64::perform, 400
m_names_x	m_out_thread_launched
seq64::perfnames, 355	seq64::perform, 401
m_names_y	m_outputing
seq64::perfnames, 355	seq64::perform, 401
seq64::perfroll, 417	m_padded_h
m_new_format	seq64::font, 162
seq64::midifile, 328	m_page_factor
m_note_length	seq64::perfroll, 417
seq64::seqedit, 468	m_pager_index
seq64::seqroll, 517	seq64::eventslots, 159
m_note_off_margin	m_painted
seq64::sequence, 568	seq64::event, 126
m_note_off_velocity	m_painting
seq64::sequence, 567	seq64::seqevent, 482
m_note_on_velocity seq64::sequence, 567	seq64::seqroll, 518
m notebook	m_parent seq64::editable_event, 105
seq64::options, 333	seq64::eventslots, 158
m notes on	seq64::perfnames, 354
seq64::sequence, 565	seq64::perfroll, 417
m_notify	seq64::perftime, 426
seq64::perform, 404	seq64::sequence, 564
m_num_in_buses	seq64::triggers, 581
seq64::mastermidibus, 281	m_pass_sysex
m_num_out_buses	seq64::rc_settings, 437
seq64::mastermidibus, 281	m_paste
m_num_poll_descriptors	seq64::seqevent, 482
seq64::mastermidibus, 282	seq64::seqroll, 518
m_number_h	m_paste_tick
seq64::seqdata, 452	seq64::triggers, 581
m_number_offset_y	m_peer_perfedit
seq64::seqdata, 452	seq64::perfedit, 346
m_number_w	m_perf
seq64::seqdata, 452	seq64::keybindentry, 216
m_numbers	m_perf_edit
seq64::seqdata, 453	seq64::mainwnd, 270
m_offset	m_perf_edit_2
seq64::font, 162	seq64::mainwnd, 270
seq64::perform, 403	m_perf_scale_x
seq64::trigger, 570	seq64::perfroll, 417
m_old	seq64::perftime, 427
seq64::seqdata, 453	m_perfnames
seq64::seqevent, 481	seq64::perfedit, 346
seq64::seqroll, 517	m_perform
m_old_progress_ticks seq64::perfroll, 418	seq64::lash, 241 m_perfroll
m_old_seq	seq64::perfedit, 346
seq64::mainwid, 258	m_perftime
m_one_measure	seq64::perfedit, 346
seq64::perform, 402	m_phase
m_options	seq64::lfownd, 244
seq64::mainwnd, 270	m_pill_width
m_optsbox	seq64::maintime, 248
seq64::eventedit, 145	m_pixmap
1 - ···, · · · ·	

seq64::font, 162	seq64::sequence, 566
seq64::gui_drawingarea_gtk2, 187	m_queued_tick
m_playback_mode	seq64::sequence, 566
seq64::perform, 401	m_raise
m_playing	seq64::sequence, 566
seq64::sequence, 566	m_range
m_playing_notes	seq64::lfownd, 244
seq64::sequence, 565	m_rank
m_playing_screen	seq64::event_list::event_key, 127
seq64::perform, 399	m_rec_vol
m_playscreen_offset	seq64::sequence, 567
seq64::perform, 399	m_recording
m_poll_descriptors	seq64::sequence, 566
seq64::mastermidibus, 282	m_red
m_pos	seq64::gui_palette_gtk2, 194
seq64::midifile, 327	m_redo_stack
seq64::seqroll, 517	seq64::triggers, 581
m_position_for_get	m_redo_vect
seq64::midi_container, 289	seq64::perform, 404
m_ppqn	m_redraw_period_ms
seq64::jack_assistant, 213	seq64::gui_window_gtk2, 198
seq64::maintime, 248	m reveal alsa ports
seq64::mainwnd, 270	seq64::rc_settings, 438
seq64::mastermidibus, 282	m_right_marker_tick
seq64::midi_splitter, 300	seq64::perftime, 427
seq64::midi_spiritor, 303	m_right_tick
seq64::midibus, 312	
•	seq64::perform, 402
seq64::midifile, 328	m_rightbox
seq64::perfedit, 347	seq64::eventedit, 145
seq64::perform, 401	m_roll_length_ticks
seq64::perfroll, 417	seq64::perfroll, 418
seq64::perftime, 427	m_running
seq64::seqedit, 468	seq64::perform, 401
seq64::seqevent, 481	m_safety_mutex
seq64::seqroll, 517	seq64::automutex, 87
seq64::seqtime, 523	m_save_user_config
seq64::sequence, 566	seq64::user_settings, 609
seq64::triggers, 581	m_scale
m print keys	seq64::seqedit, 468
seq64::rc_settings, 438	seq64::seqkeys, 490
m_priority	seq64::seqroll, 517
seq64::rc_settings, 437	m_scale_phase
m progress bar colored	seq64::Ifownd, 244
seq64::user_settings, 606	m_scale_range
m_progress_bar_thick	seq64::lfownd, 244
seq64::user settings, 606	m_scale_speed
. – •	
m_progress_color	seq64::lfownd, 244
seq64::gui_palette_gtk2, 194	m_scale_value
m_progress_height	seq64::lfownd, 244
seq64::mainwid, 259	m_scale_wave
m_progress_x	seq64::lfownd, 244
seq64::seqroll, 519	m_screen_set_notepad
m_quantized_rec	seq64::perform, 403
seq64::sequence, 566	m_screenset
m_queue	seq64::mainwid, 258
seq64::mastermidibus, 282	seq64::perform, 403
seq64::midibus, 312	m_screenset_offset
m_queued	seq64::mainwid, 258
— ·	

m_screenset_slots	seq64::user_settings, 607
seq64::mainwid, 258	m_seqdata
m_scroll_offset_key	seq64::lfownd, 244
seq64::seqkeys, 490	m_seqdata_wid
seq64::seqroll, 519	seq64::seqedit, 469
m_scroll_offset_ticks	seq64::seqevent, 481
seq64::seqdata, 452	m_seqedit
seq64::seqevent, 481	seq64::seqmenu, 497
seq64::seqroll, 519	m_seqedit_bgsequence
seq64::seqtime, 523	seq64::user_settings, 605
m_scroll_offset_x	m_seqedit_key
seq64::seqdata, 452	seq64::user_settings, 605
seq64::seqevent, 481	m_seqedit_scale
seq64::seqroll, 519	seq64::user_settings, 605
seq64::seqtime, 523	m_seqevent_wid
m_scroll_offset_y	seq64::seqedit, 470
seq64::seqkeys, 490	m_seqkeys_wid
seq64::seqroll, 519	seq64::seqedit, 469
m_selected	seq64::seqroll, 517
seq64::event, 126	m_seqroll_wid
seq64::seqevent, 481	seq64::seqedit, 470
seq64::seqroll, 517	m_seqs
seq64::trigger, 570	seq64::perform, 400
m_selecting	m_seqs_active
seq64::seqevent, 482	seq64::perform, 400
seq64::seqroll, 518	m_seqs_in_set
m_seq	seq64::perfnames, 355
seq64::eventedit, 146	seq64::perform, 403
seq64::eventslots, 158	seq64::user_settings, 608
seq64::lfownd, 243	m_seqtime_wid
seq64::mastermidibus, 282	seq64::seqedit, 469
seq64::midibus, 312	m_sequence
seq64::seqdata, 452	seq64::editable_events, 110
seq64::seqedit, 468 seq64::seqevent, 481	seq64::midi_container, 289 m sequence active
seq64::seqkeys, 490	seq64::perfnames, 355
seq64::seqroll, 517	seq64::perfroll, 419
seq64::seqtime, 523	m_sequence_count
m_seq24_interaction	seq64::perform, 403
seq64::perfroll, 419	m_sequence_max
seq64::seqevent, 481	seq64::perfnames, 355
	3cqo+pcimames, 000
·	sea64::nerform 404
m_seq_number	seq64::perform, 404
m_seq_number seq64::sequence, 567	seq64::perfroll, 419
m_seq_number seq64::sequence, 567 m_seqarea_seq_x	seq64::perfroll, 419 m_sequence_offset
m_seq_number seq64::sequence, 567 m_seqarea_seq_x seq64::mainwid, 258	seq64::perfroll, 419 m_sequence_offset seq64::perfnames, 355
m_seq_number seq64::sequence, 567 m_seqarea_seq_x seq64::mainwid, 258 seq64::user_settings, 608	seq64::perfroll, 419 m_sequence_offset seq64::perfnames, 355 seq64::perfroll, 418
m_seq_number seq64::sequence, 567 m_seqarea_seq_x seq64::mainwid, 258 seq64::user_settings, 608 m_seqarea_seq_y	seq64::perfroll, 419 m_sequence_offset seq64::perfnames, 355 seq64::perfroll, 418 m_sequence_state
m_seq_number seq64::sequence, 567 m_seqarea_seq_x seq64::mainwid, 258 seq64::user_settings, 608 m_seqarea_seq_y seq64::mainwid, 258	seq64::perfroll, 419 m_sequence_offset seq64::perfnames, 355 seq64::perfroll, 418 m_sequence_state seq64::perform, 400
m_seq_number seq64::sequence, 567 m_seqarea_seq_x seq64::mainwid, 258 seq64::user_settings, 608 m_seqarea_seq_y seq64::mainwid, 258 seq64::user_settings, 608	seq64::perfroll, 419 m_sequence_offset seq64::perfnames, 355 seq64::perfroll, 418 m_sequence_state seq64::perform, 400 m_setbox_w
m_seq_number seq64::sequence, 567 m_seqarea_seq_x seq64::mainwid, 258 seq64::user_settings, 608 m_seqarea_seq_y seq64::mainwid, 258 seq64::user_settings, 608 m_seqarea_x	seq64::perfroll, 419 m_sequence_offset seq64::perfnames, 355 seq64::perfroll, 418 m_sequence_state seq64::perform, 400 m_setbox_w seq64::eventslots, 159
m_seq_number seq64::sequence, 567 m_seqarea_seq_x seq64::mainwid, 258 seq64::user_settings, 608 m_seqarea_seq_y seq64::mainwid, 258 seq64::user_settings, 608 m_seqarea_x seq64::mainwid, 258	seq64::perfroll, 419 m_sequence_offset seq64::perfnames, 355 seq64::perfroll, 418 m_sequence_state seq64::perform, 400 m_setbox_w seq64::eventslots, 159 seq64::perfnames, 355
m_seq_number seq64::sequence, 567 m_seqarea_seq_x seq64::mainwid, 258 seq64::user_settings, 608 m_seqarea_seq_y seq64::mainwid, 258 seq64::user_settings, 608 m_seqarea_x seq64::mainwid, 258 seq64::mainwid, 258	seq64::perfroll, 419 m_sequence_offset seq64::perfnames, 355 seq64::perfroll, 418 m_sequence_state seq64::perform, 400 m_setbox_w seq64::eventslots, 159 seq64::perfnames, 355 m_show_midi
m_seq_number seq64::sequence, 567 m_seqarea_seq_x seq64::mainwid, 258 seq64::user_settings, 608 m_seqarea_seq_y seq64::mainwid, 258 seq64::user_settings, 608 m_seqarea_x seq64::mainwid, 258 seq64::mainwid, 258 seq64::mainwid, 258 seq64::user_settings, 608 m_seqarea_y	seq64::perfroll, 419 m_sequence_offset seq64::perfnames, 355 seq64::perfroll, 418 m_sequence_state seq64::perform, 400 m_setbox_w seq64::eventslots, 159 seq64::perfnames, 355 m_show_midi seq64::rc_settings, 437
m_seq_number seq64::sequence, 567 m_seqarea_seq_x seq64::mainwid, 258 seq64::user_settings, 608 m_seqarea_seq_y seq64::mainwid, 258 seq64::user_settings, 608 m_seqarea_x seq64::mainwid, 258 seq64::mainwid, 258 seq64::mainwid, 258 seq64::mainwid, 258 seq64::mainwid, 258	seq64::perfroll, 419 m_sequence_offset seq64::perfnames, 355 seq64::perfroll, 418 m_sequence_state seq64::perform, 400 m_setbox_w seq64::eventslots, 159 seq64::perfnames, 355 m_show_midi seq64::ro_settings, 437 m_show_octave_letters
m_seq_number seq64::sequence, 567 m_seqarea_seq_x seq64::mainwid, 258 seq64::user_settings, 608 m_seqarea_seq_y seq64::mainwid, 258 seq64::user_settings, 608 m_seqarea_x seq64::mainwid, 258 seq64::user_settings, 608 m_seqarea_y seq64::user_settings, 608 m_seqarea_y seq64::mainwid, 258 seq64::mainwid, 258 seq64::user_settings, 608	seq64::perfroll, 419 m_sequence_offset seq64::perfnames, 355 seq64::perfroll, 418 m_sequence_state seq64::perform, 400 m_setbox_w seq64::eventslots, 159 seq64::perfnames, 355 m_show_midi seq64::rc_settings, 437 m_show_octave_letters seq64::seqkeys, 490
m_seq_number seq64::sequence, 567 m_seqarea_seq_x seq64::mainwid, 258 seq64::user_settings, 608 m_seqarea_seq_y seq64::mainwid, 258 seq64::user_settings, 608 m_seqarea_x seq64::mainwid, 258 seq64::user_settings, 608 m_seqarea_y seq64::user_settings, 608 m_seqarea_y seq64::mainwid, 258 seq64::user_settings, 608 m_seqarea_y seq64::user_settings, 608 m_seqarea_x	seq64::perfroll, 419 m_sequence_offset seq64::perfnames, 355 seq64::perfroll, 418 m_sequence_state seq64::perform, 400 m_setbox_w seq64::eventslots, 159 seq64::perfnames, 355 m_show_midi seq64::rc_settings, 437 m_show_octave_letters seq64::seqkeys, 490 m_showbox
m_seq_number seq64::sequence, 567 m_seqarea_seq_x seq64::mainwid, 258 seq64::user_settings, 608 m_seqarea_seq_y seq64::mainwid, 258 seq64::user_settings, 608 m_seqarea_x seq64::mainwid, 258 seq64::user_settings, 608 m_seqarea_y seq64::user_settings, 608 m_seqarea_y seq64::mainwid, 258 seq64::mainwid, 258 seq64::user_settings, 608	seq64::perfroll, 419 m_sequence_offset seq64::perfnames, 355 seq64::perfroll, 418 m_sequence_state seq64::perform, 400 m_setbox_w seq64::eventslots, 159 seq64::perfnames, 355 m_show_midi seq64::rc_settings, 437 m_show_octave_letters seq64::seqkeys, 490

seq64::mainwnd, 270	seq64::event, 126
m_size_box_w	m_table
seq64::perfroll, 418	seq64::eventedit, 144
m_slot	seq64::perfedit, 346
seq64::keybindentry, 216	seq64::seqedit, 470
m_slots_chars	m_text_size_x
seq64::eventslots, 158	seq64::mainwid, 258
m_slots_x	m_text_size_y
seq64::eventslots, 159	seq64::mainwid, 258
m_slots_y	m_text_x
seq64::eventslots, 159	seq64::user_settings, 606
m_smf0_channels	m_text_y
seq64::midi_splitter, 300	seq64::user_settings, 607
m_smf0_channels_count	m_thru
seq64::midi_splitter, 300	seq64::sequence, 566
m_smf0_main_sequence	m_tick
seq64::midi_splitter, 300	seq64::maintime, 248
m_smf0_seq_number	seq64::perform, 402
seq64::midi_splitter, 300	m_tick_end
m_smf0_splitter	seq64::trigger, 570
seq64::midifile, 328	m_tick_offset
m_snap	seq64::perftime, 426
seq64::perfedit, 347	m_tick_start
seq64::perfroll, 417	seq64::trigger, 570
seq64::perftime, 427	m_ticks_per_bar
seq64::seqedit, 468	seq64::perfroll, 417
seq64::seqevent, 481	m_time_beat_width
seq64::seqroll, 517	seq64::sequence, 567
m_snap_tick	m_time_beats_per_measure
seq64::sequence, 567	seq64::sequence, 567
m_song_mute	m_timearea_y
seq64::sequence, 565	seq64::perftime, 427
m_song_start_mode	m_timeout_connect seq64::mainwnd, 272
seq64::perform, 399 seq64::rc_settings, 438	m timestamp
m speed	seq64::event, 125
seq64::lfownd, 244	seq64::event_list::event_key, 127
m_spinbutton_bpm	m_toggle_play
seq64::mainwnd, 271	seq64::seqedit, 471
m spinbutton load offset	m toggle q rec
seg64::mainwnd, 271	seq64::seqedit, 471
m_spinbutton_ss	m_toggle_record
seg64::mainwnd, 271	seq64::seqedit, 471
m_standard_bpm	m_toggle_thru
seq64::perfedit, 348	seq64::seqedit, 471
m_starting_tick	m_tooltips
seq64::perform, 402	seq64::mainwnd, 270
m_stats	seq64::options, 333
seq64::rc_settings, 437	seq64::perfedit, 347
m_status	seq64::seqedit, 471
seq64::event, 125	m_top_index
seq64::midi_control, 292	seq64::eventslots, 159
seq64::seqdata, 452	m_top_iterator
seq64::seqevent, 482	seq64::eventslots, 159
seq64::seqroll, 519	m total segs
m sysex	seq64::user_settings, 608
seq64::event, 126	m_tracks_mute_state
m_sysex_size	seq64::perform, 399
5,50/0.20	cogoponomi, coo

m_trigger_copied	m_was_playing
seq64::triggers, 581	seq64::sequence, 565
m_trigger_offset	m_wave
seq64::sequence, 566	seq64::lfownd, 244
m_triggers	m_white
seq64::sequence, 565	seq64::gui_palette_gtk2, 194
seq64::triggers, 581	m_white_pixmap
m_type	seq64::font, 162
seq64::keybindentry, 216	m_wht_key
m_undo_stack	seq64::gui_palette_gtk2, 194
seq64::triggers, 581	m_wht_paint
m_undo_vect	seq64::gui_palette_gtk2, 194
seq64::perform, 404	m_window
m_us_per_quarter_note	seq64::gui_drawingarea_gtk2, 186
seq64::perform, 402	m_window_redraw_rate_ms
seq64::sequence, 567	seq64::user_settings, 606
m_use_default_ppqn	m_window_x
seq64::midi_splitter, 300	seq64::gui_drawingarea_gtk2, 187
seq64::midifile, 328	seq64::gui_window_gtk2, 198
m_use_new_font	m_window_y
seq64::font, 162	seq64::gui_drawingarea_gtk2, 187
seq64::user_settings, 605	seq64::gui_window_gtk2, 198
m_usemidiclock	m_with_jack_master
seq64::perform, 403	seq64::rc_settings, 437
m_user_filename	m_with_jack_master_cond
seq64::rc_settings, 438	seq64::rc_settings, 438
m_user_filename_alt	m_with_jack_transport
seq64::rc_settings, 438	seq64::rc_settings, 437
m_v_page_increment	m_x
seq64::perfroll, 417	seq64::click, 90
m_v_perf_page_increment	m_xy_offset
seq64::user_settings, 606	seq64::perfnames, 355
m_vadjust	m_y
seq64::eventedit, 144	seq64::click, 90
seq64::gui_drawingarea_gtk2, 186	m_y_on_b_pixmap
seq64::perfedit, 346	seq64::font, 163
seq64::seqedit, 469	m_yellow
m_value	seq64::gui_palette_gtk2, 194
seq64::lfownd, 244	m_zoom
m_vbox	seq64::perfroll, 417
seq64::seqedit, 470	seq64::seqdata, 452
m_vector_sequence	seq64::seqedit, 468
seq64::mastermidibus, 282	seq64::seqevent, 481
m_vertical_adjust	seq64::seqroll, 517
seq64::seqroll, 517	seq64::seqtime, 523
m_vscroll	MUTE_OFF
seq64::eventedit, 145	seq64::perform, 366
seq64::perfedit, 346	MUTE_ON
m_vscroll_new	seq64::perform, 366
seq64::seqedit, 469	MUTE_TOGGLE
m_was_active_edit	seq64::perform, 366
seq64::perform, 400	maintime
m_was_active_main	seq64::maintime, 247
seq64::perform, 400	mainwid
m_was_active_names	seq64::mainwid, 252
seq64::perform, 400	mainwid_border
m_was_active_perf	seq64::user_settings, 599, 601
seq64::perform, 400	mainwid_grid_style_t

mainwid_x seq64::midl_measures, 296 mainwid_x seq64::user_settings, 599 mainwid_y seq64::sequence, 536 seq64::maintime, 247 seq64::maintime, 247 seq64::mainwid_257 seq64::sequence, 536 seq64::mainwid_257 seq64::sequence, 536 seq64::mainwid_2564 seq64::sequent_list, 132 seq64::user_settings, 436 mainwnd_cols seq64::user_settings, 599, 600 mainwid_rows seq64::user_settings, 599, 600 mid_beats_per_ lair make_clock seq64::user_settings, 602, 603 make_driceretory seq64::user_settings, 602 seq64::weent_izer seq64::user_settings, 602 mark_all seq64::weer_settings, 602 mark_all seq64::weer_settings, 602 seq64::weent_list, 133 mid_control_on mark_all seq64::weent_list, 133 mark_elected seq64::meld_init_list, 294 seq64::meld_control_opgie seq64::mid_list, 294 mid_imeasures_to_pulses seq64::mid_list, 294 mid_imeasures_to_pulses seq64::mid_list, 294 mid_imeasures_to_pulses seq64::mid_list, 29	seq64::user_settings, 597	measures
seq64:user_settings, 599 measures_to_ticks seq64:user_settings, 599 seq64:user_settings, 599 mainwid_y seq64:sequence, 536 seq64:user_settings, 599 measurestring_to_pulses seq64:mainwid_257 seq64:mainwid_257 seq64:mainwid_257 mela_string_seq64:editable_event_103 mainwid_cols seq64:will_ser_settings, 599, 600 mainwid_rows seq64:user_settings, 602, 603 mainwid_rows seq64:user_settings, 602, 603 make_clock seq64:user_settings, 602, 603 make_directory seq64:user_settings, 602 seq64:reperform, 391 seq64:user_settings, 602 mark_all seq64:reperform, 375 mark_all seq64:reperform, 375 mark_all seq64:reperform, 375 mid_control_off seq64:reperform, 3	mainwid_spacing	seq64::midi_measures, 296
seq84::user_settings, 599 seq84::sequence, 536 mainwid_y seq84::sequence, 536 seq84::mainwid, 247 seq84::mainwid, 257 seq84::mainwid, 257 seq84::delitable_event, 103 seq84::ser_settings, 436 mid_beat_widh mainwid_cols seq84::user_settings, 602, 603 seq84::user_settings, 599, 600 mid_beat_widh mainwid_rows seq84::user_settings, 602, 603 mainwid_rows seq84::user_settings, 602, 603 make_directory seq84::user_settings, 602, 603 make_directory seq84::user_settings, 602 seq84::veent_list, 134 seq64::user_settings, 602 mark_all seq64::veent_list, 134 seq64::veent_list, 133 mid_control_off seq64::veent_list, 133 mid_control_off mark_selected seq64::perform, 375 seq64::sequence, 557 mid_measures master_bus seq64::mater_midibus, 275 seq64::met_orm, 369 seq64::mid_imeasures, 296 max_sequence seq64::mid_imeasures, 296 seq64::user_settings, 602 mid_imeasures seq64::midi_control, 291 seq64::mid	seq64::user_settings, 599, 601	measures_to_ticks
seq64::user_settings, 599 seq64::sequence, 536 mainwid seq64::sequence, 536 seq64::mainwid, 257 seq64::mainwid, 257 seq64::mainwid, 257 seq64::delitable event, 103 seq64::sequence, 536 mainwid, 257 seq64::mainwid, 257 seq64::delitable event, 103 seq64::seqtings, 436 midi_beat_width mainwid cols seq64::user_settings, 602, 603 seq64::ser_settings, 599, 600 mid_beat_per_bar seq64::user_settings, 602, 603 mid_beats_per_bar seq64::user_settings, 602, 603 mid_beats_per_bar seq64::user_settings, 602, 603 mid_beats_per_minute seq64::user_settings, 602, 603 mid_beats_per_minute seq64::user_settings, 602, 603 mid_beats_per_minute seq64::user_settings, 602 mid_container seq64::user_settings, 602 mid_container seq64::user_settings, 602 mid_contoil seq64::user_settings, 602 mid_contoil seq64::revent_list, 133 mid_control_or seq64::revent_list, 133 mid_control_or seq64::revent_list, 134 seq64::mid_list, 294 seq	mainwid x	seq64, 64
mainwid_y seq64::user_settings, 599 mainwnd seq64::maintime, 247 seq64::mainwid, 257 seq64::mainwid, 257 seq64::mainwid, 264 seq64::mseffings, 436 mainwid_cols seq64::user_settings, 599, 600 mainwid_key_event seq64::user_settings, 599, 600 mainwid_cows seq64::user_settings, 599, 600 make_clook seq64::vevent, 124 make_directory seq64.figerory seq64.figerory seq64::vevent_list, 134 seq64::user_settings, 602, 603 mid_beats_per_bar seq64::user_settings, 602 mid_beats_per	seq64::user_settings, 599	seq64::sequence, 536
seq64::user_settings, 599 seq64::paintime, 247 seq64::mainwid, 257 seq64::event_list, 132 seq64::mainwid, 257 seq64::editable_event, 103 seq64::mainwid, 264 seq64::editable_event, 103 seq64::user_settings, 436 mid_beat_width mainwnd_cols seq64::user_settings, 602, 603 seq64::user_settings, 599, 600 mid_beat_per_minute seq64::user_settings, 599, 600 seq64::user_settings, 602, 603 make_clock seq64::user_settings, 602, 603 seq64::user_settings, 599, 600 mid_beats_per_minute seq64::user_settings, 602, 603 mid_beats_per_minute seq64::user_settings, 602 mid_control_con seq64::user_settings, 602 mid_control_con seq64::revent_list, 133 seq64::revent_list, 134 seq64::sevent_list, 133 seq64::revent_list, 134 seq64::sevent_list, 133 seq64::revent_list, 134 <td< td=""><td></td><td></td></td<>		
mainwnd seq64::mainwid, 267 seq64::mainwid, 267 seq64::mainwid, 264 seq64::resettings, 436 mainwnd_cols seq64::resettings, 599, 600 mainwnd_key_event seq64::perform, 391 mainwnd_rows seq64::ser_settings, 599, 600 make_clock seq64::ser_settings, 599, 600 make_clock seq64::ser_settings, 599, 600 make_clock seq64::ser_settings, 599, 600 make_clock seq64::ser_settings, 599, 600 make_setion_name seq64::perform, 391 mainwnd_rows seq64::ser_settings, 602, 603 midi_beats_per_minute seq64::user_settings, 602, 603 midi_beats_per_settings, 602, 603 midi_beats_per_minute seq64::user_settings, 602 midi_container seq64::user_settings, 602 midi_container seq64::ser_settings, 602 midi_control_ord seq64::midi_control, 290 max_seq64::sevent_list, 133 mark_out_of_range seq64::sevent_list, 133 mark_selected seq64::sevent_list, 133 mark_selected seq64::sequence, 557 seq64::midi_control, 291 max_setive_set seq64::midi_control, 291 max_setive_set seq64::user_settings, 599, 601 max_yalue seq64::user_settings, 599, 601 max_yalue seq64::user_settings, 599, 601 max_yalue seq64::user_settings, 599 mc_max_zoom seq64::user_settings, 609 mc_min_zoom seq64::user_settings, 609 mc_min_zoom seq64::user_settings, 609 mc_min_zoom seq64::user_settings, 609 mc_min_zoom seq64::user_settings, 609 midi_measures seq64::midii_control, 291 max_indii_control, 291 max_indiiid_indiiid_indiiid_indiiid_indiiid_indiii		
seq64::maintime, 247 seq64::mainwid, 257 meta_string seq64::mainwid, 264 seq64::mainwid, 264 seq64::mainwid, 264 seq64::ditable_event, 103 seq64::rc_settings, 436 midi_beat_width seq64::user_settings, 602, 603 mainwnd_cols seq64::user_settings, 602, 603 midi_beats_per_bar seq64::user_settings, 599, 600 midi_beats_per_minute seq64::user_settings, 602, 603 make_clock seq64::user_settings, 602, 603 midi_buss_override make_directory seq64::user_settings, 602 midi_buss_override make_settin_name seq64::user_settings, 602 midi_container seq64::vent_list, 134 seq64::went_list, 134 seq64::went_list, 134 mark_all seq64::went_list, 133 midi_control_on mark_all seq64::perform, 375 midi_control_toggle seq64::went_list, 133 midi_control_toggle seq64::midi_control, 290 mark_selected seq64::perform, 375 midi_measures seq64::midi_measures seq64::ment_list, 133 midi_measures seq64::midi_measures seq64::midi_measures seq64::midi_control, 291 seq64::midi_splitter		•
seq64::mainwid, 264 meta_string seq64::editable_event, 103 seq64::mainwnd, 264 seq64::editable_event, 103 meta_string seq64::editable_event, 103 mainwnd_cols seq64::user_settings, 602, 603 midi_beat_width seq64::user_settings, 602, 603 mainwnd_rows seq64::user_settings, 602, 603 midi_beats_per_minute seq64::user_settings, 602, 603 make_clock seq64::user_settings, 602, 603 midi_beats_per_minute seq64::user_settings, 602, 603 make_directory seq64::user_settings, 602 midi_container seq64::user_settings, 602, 603 make_section_name seq64::event_list, 134 seq64::event_list, 134 seq64::event_list, 134 seq64::event_list, 134 seq64::midi_control, 290 midi_control pot midi_control pot	seq64::maintime, 247	
seq64::mainwind, 264 seq64::rc_settings, 436 mainwind_cols seq64::rc_settings, 602, 603 seq64::user_settings, 599, 600 midi_beat_width seq64::user_settings, 599, 600 midi_beats_per_bar seq64::user_settings, 602, 603 seq64::user_settings, 602, 603 mainwind_rows seq64::user_settings, 602, 603 make_clock seq64::user_settings, 602, 603 seq64::event, 124 midi_buss_override make_directory seq64::user_settings, 602 make_section_name seq64::restings, 602 make_section_name seq64::restings, 599 seq64::revent_list, 134 seq64::midi_control, 290 mark_all seq64::restings, 602 mark_all seq64::perform, 375 mid_control_off seq64::perform, 375		
seq64::rc_settings, 436 midi_beat_width mainwnd_cols seq64::user_settings, 602, 603 mainwnd_key_event seq64::user_settings, 602, 603 mainwnd_rows seq64::user_settings, 602, 603 make_clock seq64::user_settings, 602, 603 make_clock seq64::user_settings, 602, 603 make_clock seq64::user_settings, 602 make_directory seq64::user_settings, 602 make_section_name seq64::mid_container seq64::rc_settings, 433, 434 midi_control mark seq64::rc_settings, 433, 434 mark seq64::rc_settings, 602 seq64::rc_settings, 433, 434 midi_control_off mark seq64::reperform, 375 mark_all seq64::perform, 375 seq64::event_list, 133 midi_control_off mark_selected seq64::perform, 375 seq64::sequence, 557 mid_measures seq64::mastermidibus, 275 seq64::midi_measures seq64::mastermidibus, 275 seq64::midi_splitter seq64::mer_settings, 599 midi_measures seq64::mer_settings, 599 midi_measures		
mainwnd_cols seq64::user_settings, 599, 600 mainwnd_key_event seq64::user_settings, 602, 603 mainwnd_rows seq64::user_settings, 602, 603 seq64::user_settings, 599, 600 mid_beats_per_minute seq64::user_settings, 599, 600 mid_buss_override make_clock seq64::user_settings, 602, 603 make_directory seq64::user_settings, 602 make_directory seq64::went_list, 134 seq64::perform, 369 seq64::meli_control_seq6 make_section_name seq64::meli_control_seq6 seq64::resettings, 433, 434 mid_control_off mark_all seq64::meli_control_off seq64::vent_list, 133 midi_control_off seq64::vent_list, 133 midi_control_toggle seq64::vent_list, 133 midi_ist seq64::vent_list, 133 midi_measures seq64::perform, 369 seq64::meli_measures master_bus seq64::meli_measures seq64::meli_control, 291 seq64::meli_measures max_sequence seq64::meli_measures seq64::meli_perform, 392 seq64::meli_meli_meli_meli_meli_seq64::meli_meli_meli_meli_meli_meli_meli_meli_	•	
seq64::user_settings, 599, 600 midi_beats_per_bar mainwnd_key_event seq64::user_settings, 602, 603 mainwnd_rows seq64::user_settings, 602, 603 make_clock seq64::user_settings, 602 seq64::user_settings, 599, 600 midi_beats_per_ininute make_clock seq64::user_settings, 602 seq64::user_settings, 609 midi_container make_directory seq64::weent_list, 134 seq64: section_name seq64::medi_container, 285 seq64: ro_settings, 433, 434 midi_control mark seq64::went_list, 134 mark seq64::event_list, 133 mark_out_of_range seq64::perform, 375 master_bus seq64::perform, 374 master_bus seq64::perform, 374 master_bus seq64::midi_list, 294 master_bus seq64::midi_measures seq64::mermidibus, 275 seq64::midi_measures seq64::mer_settings, 599 seq64::mer_settings, 602 max_sequence seq64::mer_settings, 602 max_seq4::mer_settings, 599, 601 midi_potter max_zoom seq64::mer_settings, 602		
mainwnd_key_event seq64::user_settings, 602, 603 mainwnd_rows seq64::user_settings, 602, 603 make_clock seq64::user_settings, 602, 603 make_clock seq64::user_settings, 602 make_directory seq64::user_settings, 602 make_section_name seq64::iser_settings, 602 seq64.rd mid_control manual_alsa_ports seq64::imidi_control, 290 seq64::rc_settings, 433, 434 midi_control_off mark seq64::event_list, 133 mark_all seq64::event_list, 133 seq64::event_list, 133 midi_control_off mark_selected seq64::perform, 375 seq64::perform, 375 midi_list seq64::perform, 369 seq64::midi_list, 294 master_bus seq64::perform, 369 master_bus seq64::midi_measures, 296 seq64::midi_oontrol, 291 midi_splitter max_seq64::perform, 392 seq64::midi_splitter, 298 max_sets midi_iming seq64::midi_control, 291 seq64::midi_splitter, 298 max_sets seq64::midi_splitter, 298 seq64::midi_control,		
seq64::perform, 391 midi_beats_per_minute mainwnd_rows seq64::user_settings, 602, 603 make_clock seq64::user_settings, 602 seq64::event, 124 midi_buss_override make_directory seq64::event_list, 134 seq64, 69 seq64::midi_container, 285 make_section_name seq64::midi_control seq64.*74 midi_control mark_all seq64::midi_control, 290 seq64::revent_list, 133 midi_control_of mark_all seq64::perform, 375 seq64::event_list, 133 midi_control_toggle seq64::event_list, 133 midi_control_toggle seq64::event_list, 133 midi_measures seq64::meligent seq64::midi_list, 294 mastermidibus midi_ppqn seq64::meligent seq64::meligent max_active_set midi_int		
mainwnd_rows seq64::user_settings, 602, 603 make_clock midi_buss_override seq64::user_settings, 602 seq64::user_settings, 602 make_directory seq64::event_list, 134 seq64, 69 seq64::ridi_container, 285 make_section_name seq64::ridi_control seq64, 74 midi_control manual_alsa_ports seq64::ridi_control, 290 mark_seq64::re_settings, 433, 434 midi_control_off mark seq64::reperform, 375 mark_all seq64::perform, 375 seq64::event_list, 133 midi_control_on seq64::event_list, 133 midi_control_toggle seq64::event_list, 133 midi_list seq64::event_list, 133 midi_list seq64::event_list, 133 midi_measures seq64::event_list, 133 midi_measures seq64::event_list, 133 midi_list seq64::event_list, 134 seq64::midi_measures, 296 mastermidibus seq64::midi_measures, 296 mastermidibus midi_ppqn seq64::midi_control, 291 seq64::midi_splitter, 298 max_sets	_ •	
seq64::user_settings, 599, 600 midi_buss_override make_clock seq64::user_settings, 602 make_directory seq64::event_list, 134 seq64.69 seq64::midi_container, 285 make_section_name seq64::midi_control, 290 seq64::rc_settings, 433, 434 midi_control_off mark seq64::re_settings, 433, 434 mark seq64::perform, 375 mark_all seq64::perform, 375 seq64::event_list, 133 midi_control_toggle seq64::event_list, 133 midi_ist seq64::event_list, 133 midi_measures seq64::event_list, 133 midi_measures seq64::event_list, 133 midi_measures seq64::perform, 374 midi_measures seq64::event_list, 133 midi_measures seq64::perform, 369 seq64::midi_list, 294 master_bus midi_measures seq64::mestermidibus, 275 seq64::mestermidibus, 296 seq64::midi_control, 291 midi_ppqn seq64::mestermidibus, 311 midi_ppqn seq64::mestermidibus, 201 seq64::mestermidibus, 301 max_seti		
make_clock seq64::user_settings, 602 seq64::event, 124 mid_container make_directory seq64::user_settings, 134 seq64, 69 seq64::mid_container, 285 make_section_name seq64::rtiggers, 581 seq64, 74 mid_control manual_alsa_ports seq64::rtiggers, 581 seq64::resettings, 433, 434 midi_control_off mark seq64::perform, 375 mid_control_of seq64::perform, 375 mid_control_off seq64::perform, 375 mid_control_off seq64::perform, 375 mid_control_toggle seq64::perform, 374 mid_control_toggle seq64::perform, 374 mid_ilist seq64::perform, 374 mid_ilist seq64::mid_list, 294 mid_measures seq64::mid_measures seq64::perform, 369 mid_measures master_bus seq64::mid_measures seq64::midibus mid_ppn seq64::midibus mid_splitter seq64::midi_control, 291 seq64::midi_splitter, 298 max_sets midi seq64::midi_control, 291	_	· — -
seq64::event, 124 midi_container make_directory seq64::event_list, 134 seq64, 69 seq64::midi_container, 285 make_section_name seq64::ritiggers, 581 seq64.74 midi_control manual_alsa_ports seq64::midi_control, 290 seq64::resettings, 433, 434 midi_control_ontol_ontol_ontol_on seq64::event_list, 133 midi_control_on mark_all seq64::perform, 375 seq64::event_list, 133 midi_ist mark_out_of_range seq64::perform, 374 seq64::event_list, 133 midi_ist mark_selected seq64::midi_list, 294 seq64::event_list, 133 midi_measures seq64::sequence, 557 seq64::midi_measures master_bus midi_measures seq64::mastermidibus, 275 seq64::midi_popt seq64::mastermidibus, 311 midi_popt max_active_set midi_timing seq64::midi_splitter, 298 seq64::midi_splitter, 298 max_sets seq64::midi_timing, 301 max_sets seq64::midi_tontainer, 289 seq64::midi_control, 291 seq		
make_directory seq64.69 make_section_name seq64:midi_container, 285 seq64, 74 midi_control manual_alsa_ports seq64:midi_control, 290 seq64::rc_settings, 433, 434 midi_control_off mark seq64::perform, 375 seq64::event_list, 123 midi_control_off mark_all seq64::perform, 375 seq64::event_list, 133 midi_control_toggle seq64::event_list, 133 seq64::perform, 374 mark_selcted seq64::perform, 374 seq64::event_list, 133 midi_measures seq64::sequence, 557 seq64::midi_list, 294 master_bus midi_measures seq64::perform, 369 seq64::midi_measures, 296 mastermidibus midi_ppqn seq64::meldibus, 311 seq64::meldi_ppqn seq64::midi_control, 291 seq64::midi_splitter max_active_set midi_timing seq64::melf_control, 291 seq64::midi_timing, 301 max_sets midibus seq64::midi_control, 291 seq64::midi_container, 289 max_zets midibus		
seq64, 69 seq64::midi_container, 285 make_section_name seq64::riiggers, 581 seq64, 74 midi_control manual_alsa_ports seq64::midi_control, 290 seq64::resettings, 433, 434 midi_control_off mark seq64::perform, 375 seq64::event_list, 133 midi_control_on mark_all seq64::perform, 375 seq64::event_list, 133 midi_control_toggle seq64::event_list, 133 seq64::perform, 374 mark_selected seq64::perform, 374 seq64::event_list, 133 midi_measures seq64::perform, 369 seq64::midi_measures, 296 master_bus seq64::midi_measures, 296 master_bus midi_poqn seq64::meridibus, 311 mid_poqn seq64::mastermidibus, 275 seq64::wert_list, 134 seq64::meridibus, 311 seq64::wert_list, 134 seq64::wert_settings, 602 midi_timing max_sequence seq64::midi_timing, 301 seq64::user_settings, 599 midi_timing seq64::midi_control, 291 seq64::midi_timing, 301 max_zoom midif	•	-
make_section_name seq64:triggers, 581 seq64, 74 midi_control manual_alsa_ports seq64::midi_control, 290 seq64::rc_settings, 433, 434 midi_control_off mark seq64::perform, 375 mark_all seq64::perform, 375 seq64::veent_list, 133 midi_control_on seq64::perform, 375 midi_control_toggle seq64::perform, 374 midi_list seq64::perform, 374 midi_list seq64::perform, 374 midi_list mark_ellctd seq64::perform, 374 seq64::perform, 374 midi_list midi_list seq64::midi_list, 294 midi_measures seq64::midi_measures, 296 master_bus seq64::midi_measures, 296 master_bus seq64::midi_measures, 296 master_midibus midi_measures_to_pulses seq64::mellous, 311 midi_ppqn max_active_set midi_splitter seq64::mellous, 311 seq64::weent_list, 134 seq64::mellous, 392 seq64::weent_list, 134 seq64::mellous, 392 seq64::mellous, 301 <td< td=""><td>_</td><td>-</td></td<>	_	-
seq64, 74 midi_control manual_alsa_ports seq64::midi_control, 290 mark midi_control_off seq64::revent, 123 midi_control_on mark_all seq64::perform, 375 seq64::event_list, 133 midi_control_toggle seq64::veent_list, 133 midi_control_toggle seq64::event_list, 133 midi_list seq64::event_list, 133 midi_measures seq64::event_list, 133 seq64::midi_list, 294 maker_bus seq64::midi_measures, 296 master_bus midi_measures seq64::sequence, 557 seq64::midi_measures, 296 master_bus midi_measures_to_pulses seq64::mastermidibus, 275 seq64::user_settings, 602 maxeq64::midi_control, 291 seq64::user_settings, 602 max_active_set midi_splitter seq64::midi_timing seq64::midi_timing seq64::midi_vector, 305 seq64::midi_vector, 305 max_sets seq64::midi_vector, 305 seq64::midi_control, 291 seq64::midi_vector, 305 max_zoom seq64::midi_container, 289 seq64::midi_control, 29		· —
manual_alsa_ports seq64::midi_control, 290 seq64::rc_settings, 433, 434 midi_control_off mark seq64::perform, 375 mark_all seq64::perform, 375 seq64::event_list, 133 midi_control_toggle seq64::event_list, 133 seq64::perform, 374 mark_selected seq64::midi_list, 294 seq64::event_list, 133 midi_measures seq64::perform, 369 seq64::midi_measures, 296 master_bus midi_measures seq64::perform, 369 seq64::midi_measures, 296 mastermidibus midi_papa seq64::mastermidibus, 275 seq64::ser_settings, 602 seq64::midi_control, 291 seq64::ser_settings, 602 max_active_set midi_timing seq64::ser_settings, 599 seq64::midi_timing, 301 max_sets seq64::midi_timing, 301 seq64::user_settings, 599, 601 seq64::midi_timing, 301 max_zets seq64::midi_timing, 301 seq64::user_settings, 602 seq64::midi_timing, 308, 309 max_zoom seq64::midi_container, 289 seq64::midi_container, 289 seq64::midifile, 315 <td></td> <td></td>		
seq64::rc_settings, 433, 434 midi_control_off mark seq64::perform, 375 mark_all seq64::perform, 375 seq64::event_list, 133 midi_control_toggle mark_out_of_range seq64::perform, 374 seq64::event_list, 133 midi_list mark_selected seq64::midi_list, 294 seq64::perform, 369 seq64::midi_measures, 296 master_bus midi_measures seq64::perform, 369 midi_measures, 296 mastermidibus midi_ppqn seq64::mastermidibus, 275 seq64::user_settings, 602 meq64::midi_control, 291 midi_splitter max_active_set midi_timing seq64::midi_splitter, 298 midi_timing seq64::midi_timing, 301 midi_vector seq64::user_settings, 599 midi_timing max_sets midibus seq64::user_settings, 599, 601 seq64::midi_timing, 301 max_value seq64::midi_control, 291 seq64::midi_control, 291 seq64::midi_control, 291 max_zoom seq64::midi_control, 289 seq64::mer_settings, 609 seq64::mid	•	_
mark seq64::perform, 375 seq64::event, 123 midi_control_on mark_all seq64::perform, 375 seq64::event_list, 133 midi_control_toggle seq64::perform, 374 seq64::perform, 374 seq64::event_list, 133 midi_list seq64::perform, 374 seq64::midi_list, 294 seq64::perform, 374 midi_list seq64::perform, 374 midi_list seq64::midi_list, 294 midi_measures seq64::perform, 374 midi_list seq64::midi_list, 294 midi_measures seq64::perform, 369 midi_measures master_bus seq64::midi_measures, 296 master_bus midi_measures, 296 master_bus seq64::midi_measures, 296 midi_measures seq64::midi_measures, 296 midi_measures seq64::midi_pop seq64::mastermidibus, 369 midi_splitter maseq64::mer_settings, 602 midi_splitter max_sets seq64::midi_timing, 301 max_velue seq64::midi_timing, 308, 309 max_lever_settings, 602 seq64::midi_timing, 301		
seq64::event, 123 midi_control_on mark_all seq64::perform, 375 seq64::event_list, 133 midi_control_toggle seq64::event_list, 133 seq64::perform, 374 mark_selected seq64::perform, 374 seq64::event_list, 133 midi_list seq64::event_list, 133 midi_measures seq64::sequence, 557 seq64::midi_measures, 296 master_bus midi_measures_to_pulses seq64::seqform, 369 midi_plopqn mastermidibus midi_ppqn seq64::mastermidibus, 275 seq64:user_settings, 602 max_eq64::midi_control, 291 mid_splitter max_active_set midi_timing seq64::merform, 392 seq64::midi_splitter, 298 max_sequence midi_timing seq64::user_settings, 599 midibus seq64::user_settings, 599, 601 midibus seq64::midi_control, 291 seq64::midi_vector, 305 max_value seq64::midi_control, 291 max_zoom seq64::midille, 315 seq64::user_settings, 602 seq64::midifile, 315 seq64::user_settings, 609		
mark_all seq64::perform, 375 seq64::event_list, 133 midi_control_toggle mark_out_of_range seq64::perform, 374 seq64::event_list, 133 midi_list mark_selected seq64::midi_list, 294 seq64::event_list, 133 midi_measures seq64::sequence, 557 seq64::midi_measures, 296 master_bus midi_measures_to_pulses seq64::perform, 369 midi_measures_to_pulses seq64::mastermidibus midi_ppqn seq64::mastermidibus, 275 seq64::user_settings, 602 max_active_set midi_splitter seq64::midi_control, 291 seq64::event_list, 134 max_active_set midi_timing seq64::perform, 392 seq64::midi_timing, 301 max_sequence midi_vector seq64::user_settings, 599 seq64::midi_vector, 305 max_sets midibus seq64::user_settings, 599, 601 seq64::midi_control, 291 max_zoom seq64::midi_container, 289 seq64::user_settings, 602 seq64::midile, 315 seq64::user_settings, 609 seq64::midilong seq64::user_s		
seq64::event_list, 133 midi_control_toggle mark_out_of_range seq64::perform, 374 seq64::event_list, 133 midi_list mark_selected seq64::midi_list, 294 seq64::event_list, 133 midi_measures seq64::event_list, 133 seq64::midi_measures, 296 master_bus seq64::midi_measures, 296 seq64::perform, 369 midi_measures_to_pulses seq64::perform, 369 seq64.58 mastermidibus midi_ppqn seq64::mastermidibus, 275 seq64::user_settings, 602 max_eq64::midi_control, 291 midi_splitter max_active_set midi_splitter seq64::midi_control, 291 seq64::midi_timing, 301 max_sequence seq64::midi_vector seq64::user_settings, 599 midibus seq64::user_settings, 599, 601 seq64::midi_vector, 305 max_sets midibus seq64::midi_control, 291 seq64::midibus, 308, 309 max_zoom seq64::midi_container, 289 seq64::midiple, 315 seq64::midifile, 315 seq64::midiple, 315 seq64::midiple, 315 seq64::mid	•	
mark_out_of_range seq64::perform, 374 seq64::event_list, 133 midi_list mark_selected seq64::midi_list, 294 seq64::sequence, 557 midi_measures master_bus seq64::midi_measures, 296 master_bus midi_ppqn seq64::perform, 369 seq64:midi_ppqn seq64::mastermidibus, 275 seq64::user_settings, 602 seq64::midibus, 311 midi_ppqn match seq64::werl_list, 134 seq64::midi_control, 291 seq64::werl_list, 134 seq64::midi_splitter seq64::midi_splitter, 298 max_active_set midi_timing seq64::midi_timing, 301 seq64::midi_timing, 301 max_sequence midi_vector seq64::user_settings, 599 seq64::midi_bus, 308, 309 max_sets midibus seq64::midi_control, 291 seq64::midibus, 308, 309 max_value midibyte seq64::midi_control, 291 seq64::midifile max_zoom seq64::midifile, 315 seq64::user_settings, 609 seq64::midiong mc_max_zoom seq64::midiong		
seq64::event_list, 133 midi_list mark_selected seq64::midi_list, 294 seq64::event_list, 133 midi_measures seq64::sequence, 557 seq64::midi_measures, 296 master_bus seq64::pulses seq64::pulses seq64; 58 mastermidibus midi_ppqn seq64::mastermidibus, 275 seq64::user_settings, 602 seq64::midi_control, 291 midi_splitter match seq64::event_list, 134 seq64::midi_control, 291 seq64::midi_splitter, 298 max_active_set midi_timing seq64::midi_splitter, 298 midi_timing, 301 max_sequence midi_vector seq64::midi_vector, 305 seq64::midi_vector, 305 max_sets midibus seq64::user_settings, 599, 601 seq64::midibus, 308, 309 max_value midibyte seq64::midi_control, 291 seq64::midi_container, 289 mc_baseline_ppqn seq64::midi_container, 289 seq64::midi_container, 289 seq64::midifile, 315 seq64::midi_container, 289 seq64::midifile, 315 seq64::midi_nontainer, 289	· —	
mark_selected seq64::midi_list, 294 seq64::event_list, 133 midi_measures seq64::sequence, 557 seq64::midi_measures, 296 master_bus midi_measures_to_pulses seq64::perform, 369 seq64, 58 mastermidibus midi_ppqn seq64::mastermidibus, 275 seq64::user_settings, 602 seq64::midibus, 311 midi_splitter match seq64::weent_list, 134 seq64::midi_control, 291 seq64::midi_splitter, 298 max_active_set midi_timing seq64::perform, 392 seq64::midi_timing, 301 max_sequence midi_vector seq64::user_settings, 599 midibus seq64::user_settings, 599, 601 seq64::midi_vector, 305 max_value midibus seq64::midi_control, 291 seq64::midibus, 308, 309 max_zoom seq64::midi_container, 289 seq64::user_settings, 602 seq64::midifile, 315 seq64::user_settings, 609 seq64::riggers, 581 mc_max_zoom seq64::riggers, 581 seq64::user_settings, 609 midilong seq64::rigers, 581 <		
seq64::event_list, 133 seq64::sequence, 557 master_bus seq64::perform, 369 mastermidibus seq64::mastermidibus, 275 seq64::midi_ppqn seq64::midi_splitter match seq64::midi_control, 291 max_active_set seq64::user_settings, 599 max_sets seq64::user_settings, 599, 601 max_value seq64::midi_control, 291 max_zoom seq64::user_settings, 602 me_baseline_ppqn seq64::user_settings, 609 mc_max_zoom seq64::user_settings, 609 mc_max_zoom seq64::user_settings, 609 mc_max_zoom seq64::user_settings, 609 mc_max_zoom seq64::user_settings, 609 mc_min_zoom seq64::user_settings, 609 mc_min_zoom seq64::user_settings, 609 midilong seq64::triggers, 581 midilong seq64, 51		_
seq64::sequence, 557 master_bus seq64::perform, 369 mastermidibus seq64::mastermidibus, 275 seq64::midi_ppqn seq64::molippqn seq64::midi_splitter match seq64::midi_control, 291 max_active_set seq64::perform, 392 max_sequence seq64::user_settings, 599 max_sets seq64::user_settings, 599 max_value seq64::midi_control, 291 max_zoom seq64::user_settings, 602 mc_baseline_ppqn seq64::user_settings, 609 mc_max_zoom seq64::user_settings, 609 mc_max_zoom seq64::user_settings, 609 mc_max_zoom seq64::user_settings, 609 mc_min_zoom seq64::user_settings, 609 midilong mc_min_zoom seq64::user_settings, 609 midilong seq64::triggers, 581 midilong seq64::gefform, 398 seq64::gef64::gefform, 398 seq64::gef64::gefform, 398 seq64::gef64::gefform, 398 seq64::gef64::gefform, 398 seq64::gefform, 3	-	
master_busmidi_measures_to_pulsesseq64::perform, 369seq64, 58mastermidibusmidi_ppqnseq64::mastermidibus, 275seq64::user_settings, 602seq64::midibus, 311midi_splittermatchseq64::event_list, 134seq64::midi_control, 291seq64::midi_splitter, 298max_active_setmidi_timingseq64::perform, 392seq64::midi_timing, 301max_sequencemidi_vectorseq64::user_settings, 599seq64::midi_vector, 305max_setsmidibusseq64::user_settings, 599, 601seq64::midibus, 308, 309max_valuemidibyteseq64::midi_control, 291seq64, 51max_zoommidifileseq64::user_settings, 602seq64::midi_container, 289mc_baseline_ppqnseq64::midifile, 315seq64::user_settings, 609seq64::midifile, 315seq64::user_settings, 609midilongmc_max_zoomseq64::triggers, 581mc_min_zoomseq64, 51	• —	
seq64::perform, 369 mastermidibus seq64::mastermidibus, 275 seq64::mastermidibus, 311 match seq64::midi_control, 291 max_active_set seq64::perform, 392 max_sequence seq64::user_settings, 599 max_sets seq64::user_settings, 599, 601 max_value seq64::midi_control, 291 max_zoom seq64::user_settings, 602 mc_baseline_ppqn seq64::user_settings, 609 mc_max_zoom seq64::user_settings, 609 mc_max_zoom seq64::user_settings, 609 mc_max_zoom seq64::user_settings, 609 mc_min_zoom seq64::user_settings, 609 mc_min_zoom seq64::user_settings, 609 mc_min_zoom seq64::user_settings, 609 mc_min_zoom seq64::user_settings, 609 midilong seq64, 51 midilong seq64, 51 midilong seq64, 51 midilong seq64, 51		
mastermidibusmidi_ppqnseq64::mastermidibus, 275seq64::user_settings, 602seq64::midibus, 311midi_splittermatchseq64::event_list, 134seq64::midi_control, 291seq64::midi_splitter, 298max_active_setmidi_timingseq64::perform, 392seq64::midi_timing, 301max_sequenceseq64::midi_vectorseq64::user_settings, 599seq64::midibusmax_setsmidibusseq64::user_settings, 599, 601seq64::midibus, 308, 309max_valuemidibyteseq64::midi_control, 291seq64::midiflemax_zoommidifileseq64::user_settings, 602seq64::midi_container, 289mc_baseline_ppqnseq64::midifle, 315seq64::user_settings, 609seq64::midilongmc_max_zoomseq64::riggers, 581seq64::user_settings, 609midilongmc_min_zoomseq64, 51		_
seq64::mastermidibus, 275 seq64::midibus, 311 match seq64::midi_control, 291 max_active_set seq64::perform, 392 max_seq64::user_settings, 599 max_sets seq64::user_settings, 599, 601 max_value seq64::midi_control, 291 max_zoom seq64::user_settings, 602 mc_baseline_ppqn seq64::user_settings, 609 mc_max_zoom seq64::user_settings, 609 mc_min_zoom midilong seq64::user_settings, 609 midilong seq64::user_settings, 609 midilong seq64::user_settings, 609 midilong seq64::user_settings, 609 midilong seq64, 51		•
seq64::midibus, 311 match seq64::midi_control, 291 max_active_set seq64::perform, 392 max_seq64::user_settings, 599 max_sets seq64::user_settings, 599, 601 max_value seq64::midi_control, 291 max_zoom seq64::user_settings, 602 mc_baseline_ppqn seq64::user_settings, 609 mc_max_zoom seq64::user_settings, 609 mc_max_zoom seq64::user_settings, 609 mc_min_zoom seq64::user_settings, 609 mc_min_zoom seq64::user_settings, 609 mc_min_zoom seq64::user_settings, 609 mc_min_zoom seq64::user_settings, 609 mc_min_zoom seq64::user_settings, 609 mc_min_zoom seq64::user_settings, 609 mc_min_zoom seq64::user_settings, 609 mc_min_zoom seq64::user_settings, 609 mc_min_zoom seq64::user_settings, 609 midilong seq64, 51		
match seq64::midi_control, 291 seq64::midi_splitter, 298 max_active_set midi_timing seq64::midi_timing, 301 max_sequence seq64::user_settings, 599 seq64::midi_vector, 305 max_sets midibus seq64::midi_control, 291 seq64::midi_control, 291 seq64::midi_control, 291 seq64::user_settings, 602 seq64::midi_container, 289 mc_baseline_ppqn seq64::user_settings, 609 seq64::midile, 315 seq64::user_settings, 609 mc_max_zoom seq64::user_settings, 609 midilong mc_min_zoom seq64: midilong seq64: seq64::midiong seq64::triggers, 581 midilong seq64, 51	•	•
seq64::midi_control, 291 max_active_set	•	_ ·
max_active_set midi_timing seq64::perform, 392 seq64::midi_timing, 301 max_sequence midi_vector seq64::midi_vector, 305 max_sets midibus seq64::midibus, 308, 309 max_value seq64::midi_control, 291 seq64::midile seq64::user_settings, 602 midifile seq64::user_settings, 602 seq64::midi_container, 289 mc_baseline_ppqn seq64::midifile, 315 seq64::user_settings, 609 seq64::perform, 398 mc_max_zoom seq64::user_settings, 609 mc_max_zoom seq64::triggers, 581 midilong mc_min_zoom seq64, 51		•
seq64::perform, 392 max_sequence seq64::user_settings, 599 max_sets seq64::user_settings, 599, 601 max_value seq64::midi_control, 291 max_zoom seq64::user_settings, 602 mc_baseline_ppqn seq64::user_settings, 609 mc_max_zoom seq64::user_settings, 609 mc_max_zoom seq64::user_settings, 609 mc_min_zoom seq64::user_settings, 609 midilong mc_min_zoom seq64, 51	• —	. – .
max_sequencemidi_vectorseq64::user_settings, 599seq64::midi_vector, 305max_setsmidibusseq64::user_settings, 599, 601seq64::midibus, 308, 309max_valuemidibyteseq64::midi_control, 291seq64, 51max_zoommidifileseq64::user_settings, 602seq64::midi_container, 289mc_baseline_ppqnseq64::midifile, 315seq64::user_settings, 609seq64::perform, 398mc_max_zoomseq64::triggers, 581me_min_zoomseq64, 51		
seq64::user_settings, 599 max_sets seq64::user_settings, 599, 601 max_value seq64::midibus, 308, 309 max_value seq64::midibus, 308, 309 midibyte seq64::midifile seq64::midifile seq64::midifile, 315 seq64::midibus, 308, 309 midifile seq64::midious, 308, 309 seq64::midious, 308, 309 midifile seq64::midious, 308, 309 midifile seq64::midious, 308, 309 m	·	
max_setsmidibusseq64::user_settings, 599, 601seq64::midibus, 308, 309max_valuemidibyteseq64::midi_control, 291seq64, 51max_zoommidifileseq64::user_settings, 602seq64::midi_container, 289mc_baseline_ppqnseq64::midifile, 315seq64::user_settings, 609seq64::perform, 398mc_max_zoomseq64::triggers, 581seq64::user_settings, 609midilongmc_min_zoomseq64, 51	_ ·	_
seq64::user_settings, 599, 601 seq64::midibus, 308, 309 max_value midibyte seq64::midi_control, 291 seq64, 51 max_zoom midifile seq64::user_settings, 602 seq64::midi_container, 289 mc_baseline_ppqn seq64::midifile, 315 seq64::user_settings, 609 seq64::perform, 398 mc_max_zoom seq64::triggers, 581 seq64::user_settings, 609 midilong mc_min_zoom seq64, 51		· —
max_valuemidibyteseq64::midi_control, 291seq64, 51max_zoommidifileseq64::user_settings, 602seq64::midi_container, 289mc_baseline_ppqnseq64::midifile, 315seq64::user_settings, 609seq64::perform, 398mc_max_zoomseq64::triggers, 581seq64::user_settings, 609midilongmc_min_zoomseq64, 51		
seq64::midi_control, 291seq64, 51max_zoommidifileseq64::user_settings, 602seq64::midi_container, 289mc_baseline_ppqnseq64::midifile, 315seq64::user_settings, 609seq64::perform, 398mc_max_zoomseq64::triggers, 581seq64::user_settings, 609midilongmc_min_zoomseq64, 51	. – • • • • • • • • • • • • • • • • • •	
max_zoommidifileseq64::user_settings, 602seq64::midi_container, 289mc_baseline_ppqnseq64::midifile, 315seq64::user_settings, 609seq64::perform, 398mc_max_zoomseq64::triggers, 581seq64::user_settings, 609midilongmc_min_zoomseq64, 51		-
seq64::user_settings, 602 seq64::midi_container, 289 mc_baseline_ppqn seq64::midifile, 315 seq64::user_settings, 609 seq64::perform, 398 mc_max_zoom seq64::triggers, 581 seq64::user_settings, 609 midilong mc_min_zoom seq64, 51	• —	
mc_baseline_ppqn seq64::midifile, 315 seq64::user_settings, 609 seq64::perform, 398 mc_max_zoom seq64::triggers, 581 seq64::user_settings, 609 midilong mc_min_zoom seq64, 51	_	
seq64::user_settings, 609 mc_max_zoom seq64::triggers, 581 seq64::user_settings, 609 mc_min_zoom seq64, 51		•
mc_max_zoom seq64::triggers, 581 seq64::user_settings, 609 midilong mc_min_zoom seq64, 51		•
seq64::user_settings, 609 midilong mc_min_zoom seq64, 51		• •
mc_min_zoom seq64, 51		
		•
seq64::user_settings, 609 midipulse		•
	seq64::user_settings, 609	midipulse

seq64, 51	moving
midishort	seq64::seqroll, 514
seq64, 51	musical_key
min	seq64::sequence, 561
seq64, 74 min_value	musical_scale seq64::sequence, 561
seq64::midi_control, 291	mute_all_tracks
min zoom	seq64::perform, 384
seq64::user_settings, 602	seq64::seqmenu, 496
mod_control	mute_group_offset
seq64::click, 90	seq64::perform, 394
seq64::keystroke, 239	mute_group_tracks
mod_control_shift	seq64::perform, 377
seq64::click, 90	mute_op_t
seq64::keystroke, 239	seq64::perform, 366
mod_last_tick	mute_screenset
seq64::sequence, 538	seq64::perform, 384
mod_super	mutex
seq64::click, 90	seq64::mutex, 330
seq64::keystroke, 239	name
mod_timestamp	seq64::sequence, 537
seq64::event, 120	seq64::user_instrument, 583
modifier	seq64::user_midi_bus, 587
seq64::click, 90	name_change_callback
seq64::keystroke, 238	seq64::seqedit, 463
modify	name_to_value
seq64::perform, 367 seq64::sequence, 534	seq64::editable_event, 101
modify_current_event	new_current_sequence
seq64::eventslots, 153	seq64::seqmenu, 494
motion_notify	new_file
seq64::seqroll, 512	seq64::mainwnd, 268
mouse_action	new_open_error_dialog
seq64::seqedit, 466	seq64::mainwnd, 268
mouse_action_e	new_sequence seq64::perform, 370
seq64, 54	seq64::seqmenu, 494
mouse_fruity_callback	next
seq64::options, 333	seq64::triggers, 580
mouse_mod4_callback	next_data_line
seq64::options, 333	seq64::configfile, 94
mouse_seq24_callback	next_trigger
seq64::options, 332	seq64::triggers, 580
mouse_snap_split_callback	normal_action
seq64::options, 333	seq64::seqroll, 513
move	normalize
seq64::triggers, 578	seq64::user_settings, 597
move_selected seq64::triggers, 577	note_off_length
move_selected_notes	seq64::seqroll, 504
seq64::seqroll, 510	note_off_margin
seq64::sequence, 552	seq64::sequence, 562 number
move_selected_triggers_to	
seq64::sequence, 545	seq64::sequence, 534
move_selection_box	off_playing_notes
seq64::seqroll, 510	seq64::sequence, 558
move_triggers	off_queued
seq64::perform, 373	seq64::sequence, 539
seq64::sequence, 546	off_sequences

seq64::perform, 379	seq64::eventedit, 144
offset	seq64::eventslots, 158
seq64::trigger, 570	seq64::mainwid, 257
on_button_press_event	seq64::perfroll, 416
seq64::AbstractPerfInput, 86	seq64::seqedit, 466
seq64::FruityPerfInput, 165	seq64::seqevent, 480
seq64::FruitySeqEventInput, 169	seq64::seqroll, 515
seq64::FruitySeqRollInput, 171	on_focus_out_event
seq64::Seq24PerfInput, 441	seq64::eventedit, 144
seq64::Seq24SeqEventInput, 443	seq64::eventslots, 158
seq64::eventslots, 158	seq64::lfownd, 243
seq64::mainwid, 256	seq64::mainwid, 257
seq64::perfnames, 352	seq64::perfroll, 416
seq64::perfroll, 415	seq64::seqedit, 466
seq64::perftime, 425	seq64::seqevent, 480
seq64::seqdata, 450	seq64::seqroll, 515
seq64::seqevent, 479	on_frame_down
seq64::seqkeys, 488	seq64::eventslots, 158
seq64::seqroll, 514	on_frame_end
seq64::seqtime, 523	seq64::eventslots, 158
on_button_release_event	on_frame_home
seq64::AbstractPerfInput, 86	seq64::eventslots, 158
seq64::FruityPerfInput, 165	on_frame_up
seq64::FruitySeqEventInput, 169	seq64::eventslots, 158
seq64::FruitySeqRollInput, 171	on_grouplearnchange
seq64::Seq24PerfInput, 441	seq64::mainwnd, 269
seq64::Seq24SeqEventInput, 444	seq64::performcallback, 406
seq64::eventslots, 158	on_key_press_event
seq64::mainwid, 256	seq64::eventedit, 144
seq64::perfnames, 352	seq64::keybindentry, 216
seq64::perfroll, 415	seq64::mainwnd, 269
seq64::perftime, 426	seq64::perfedit, 345
seq64::seqdata, 450	seq64::perfroll, 416
seq64::seqevent, 479	seq64::seqedit, 467
seq64::seqkeys, 488	seq64::seqevent, 480
seq64::seqroll, 514	seq64::seqroll, 515
seq64::seqtime, 523	on_key_release_event
on_delete_event	seq64::mainwnd, 269
seq64::eventedit, 144	on_leave_notify_event
seq64::mainwnd, 269	seq64::seqdata, 451
seq64::perfedit, 345	seq64::seqkeys, 489
seq64::seqedit, 466	seq64::seqroll, 516
on_enter_notify_event	on_left_button_pressed
seq64::seqkeys, 489	seq64::FruityPerfInput, 166
seq64::seqroll, 516	on_motion_notify_event
on_expose_event	seq64::AbstractPerfInput, 86
seq64::eventslots, 157	seq64::FruityPerfInput, 165
seq64::maintime, 247	seq64::FruitySeqEventInput, 170
seq64::mainwid, 256	seq64::FruitySeqRollInput, 171
seq64::perfnames, 352	seq64::Seq24PerfInput, 441
seq64::perfroll, 415	seq64::Seq24SeqEventInput, 444
seq64::perftime, 425	seq64::mainwid, 257
seq64::seqdata, 450	seq64::perfroll, 415
seq64::seqevent, 479	seq64::seqdata, 451
seq64::seqkeys, 488	seq64::seqevent, 479
seq64::seqroll, 514	seq64::seqkeys, 489
seq64::seqtime, 522	seq64::seqroll, 514
on_focus_in_event	on_move_down

seq64::eventslots, 158	operator=
on_move_up	seq64::automutex, 87
seq64::eventslots, 158	seq64::click, 89
on_queued	seq64::editable_event, 101
seq64::sequence, 539	seq64::editable_events, 108
on_realize	seq64::event, 117
seq64::eventedit, 143	seq64::event_list, 130
seq64::eventslots, 157	seq64::gui_drawingarea_gtk2, 179
seq64::gui_drawingarea_gtk2, 186	seq64::keystroke, 237
seq64::gui_window_gtk2, 197	seq64::maintime, 247
seq64::maintime, 247	seq64::rc_settings, 432
seq64::mainwid, 255	seq64::sequence, 534
seq64::perfedit, 345	seq64::triggers, 574
seq64::perfnames, 352	seq64::user_instrument, 583
seq64::perfroll, 414	seq64::user_midi_bus, 587
seq64::perftime, 425	seq64::user_settings, 597
seq64::seqdata, 450	options
seq64::seqedit, 466	seq64::keybindentry, 216
seq64::seqevent, 479	seq64::keys_perform, 230
seq64::seqkeys, 488	seq64::options, 332
seq64::seqmenu, 497	seq64::perform, 398
seq64::seqroll, 514	seq64::rc_settings, 436
seq64::seqtime, 522	options_dialog
on_right_button_pressed	seq64::mainwnd, 267
seq64::FruityPerfInput, 166	optionsfile
on_scroll_event	seq64::keys_perform, 230
seq64::eventslots, 158	seq64::optionsfile, 335
seq64::perfnames, 354	seq64::perform, 398
seq64::perfroll, 416	seq64::rc_settings, 436
seq64::seqdata, 451	orange
seq64::seqedit, 467	seq64::gui_palette_gtk2, 193
seq64::seqkeys, 489	output
seq64::seqroll, 516	seq64::jack_assistant, 205
on_set_focus	output_func
seq64::eventedit, 143	seq64::perform, 385
seq64::seqedit, 466	output_thread_func
on_size_allocate	seq64, 73
seq64::eventslots, 158	padded_height
seq64::perfnames, 354	seq64::font, 162
seq64::perfroll, 416	page_movement
seq64::perftime, 426	seq64::eventslots, 156
seq64::seqdata, 451	page_topper
seq64::seqevent, 480	seq64::eventslots, 156
seq64::seqkeys, 489	pager_index
seq64::seqroll, 516	seq64::eventslots, 151
seq64::seqtime, 523	paint
on_size_request	seq64::event, 123
seq64::perfroll, 416	parent
open_file	seq64::editable_event, 101
seq64::mainwnd, 264	seq64::jack_assistant, 201
open_performance_edit	parse
seq64::mainwnd, 266	seq64::configfile, 95
open_performance_edit_2	seq64::midifile, 316
seq64::mainwnd, 266	seq64::optionsfile, 335
operator<	seq64::userfile, 611
seq64::event, 117	parse_command_line_options
seq64::event_list::event_key, 127	seq64, 66
seq64::trigger, 569	seq64::rc_settings, 436
Jequingger, Juj	354040_35kiiny3, 430

parse_options_files	perftime
seq64, 65	seq64::perftime, 422
parse_prop_header	pixel_to_tick
seq64::midifile, 318	seq64::perftime, 424
parse_proprietary_track	play
seq64::midifile, 319	seq64::mastermidibus, 280
parse_smf_0	seq64::midibus, 310
seq64::midifile, 317	seq64::perform, 382
parse_smf_1	seq64::sequence, 541
seq64::midifile, 318	seq64::triggers, 574
partial_assign	play_change_callback
seq64::sequence, 534	seq64::seqedit, 463
pass_sysex	play_note_off
seq64::rc_settings, 433, 434	seq64::sequence, 558
paste	play_note_on
seq64::triggers, 577 paste selected	seq64::sequence, 558
seq64::sequence, 550	playback_key_event seq64::perform, 392
paste_trigger	poll_for_midi
seq64::sequence, 545	seq64::mastermidibus, 278
pattern_edit	pop_redo
seq64::keys_perform, 225, 226	seq64::sequence, 535
pause	seq64::triggers, 574
seq64::keys_perform, 225	pop_trigger_redo
seq64::sequence, 558	seq64::perform, 374
pause_key	seq64::sequence, 536
seq64::perform, 389	pop_trigger_undo
pause_playing	seq64::perform, 373
seq64::mainwnd, 266	seq64::sequence, 536
seq64::perfedit, 345	pop_undo
seq64::perform, 389	seq64::sequence, 535
perf	seq64::triggers, 574
seq64::gui_drawingarea_gtk2, 180	popup_event_menu
seq64::gui_window_gtk2, 197	seq64::seqedit, 465
seq64::options, 332	popup_menu
perf_h_page_increment	seq64::perfedit, 344
seq64::user_settings, 600, 602	seq64::seqedit, 465
perf_modify	seq64::seqmenu, 494
seq64::eventedit, 142	popup_midibus_menu
perf_v_page_increment	seq64::seqedit, 465
seq64::user_settings, 600, 602	popup_midich_menu
perfedit	seq64::seqedit, 465
seq64::perfedit, 342	popup_sequence_menu
seq64::perfnames, 354	seq64::seqedit, 465
seq64::perfroll, 417	popup_tool_menu
seq64::perftime, 426	seq64::seqedit, 465
perfnames 250	port_exit
seq64::perfnames, 350	seq64::mastermidibus, 280
perform	port_start
seq64::keys_perform, 230 seq64::perform, 367	seq64::mastermidibus, 280 position
seq64::sequence, 564	seq64::jack_assistant, 204
perfroll	seq64::midi_container, 286
seq64::FruityPerfInput, 167	position_increment
seq64::Seq24PerfInput, 442	seq64::midi_container, 286
seq64::perfroll, 411	position_jack
perfroll_key_event	seq64::perform, 379
seq64::perform, 392	position_reset
· · · · · · · · · · · · · · · · · · ·	. –

seq64::midi_container, 286	put
pow2	seq64::midi_container, 286
seq64::midifile, 320	seq64::midi_list, 295
ppqn	seq64::midi_vector, 306
seq64::mainwnd, 265	put_event_on_bus
seq64::midi splitter, 299	seq64::sequence, 562
seq64::midi_timing, 302	
seq64::midifile, 317	q_rec_change_callback
ppqn_is_valid	seq64::seqedit, 464
seq64, 69	quantize_events
print	seq64::sequence, 560
seq64::event, 125	query_save_changes
seq64::event_list, 134	seq64::mainwnd, 267
seq64::mastermidibus, 277	queue
seq64::midibus, 310	seq64::keys_perform, 223
seq64::sequence, 541	quit
seq64::triggers, 574	seq64::gui_assistant, 173
print_keys	seq64::gui_assistant_gtk2, 175
seq64::rc_settings, 433, 434	seq64::gui_window_gtk2, 197
print_triggers	
seq64::perform, 372	rc
seq64::sequence, 541	seq64, 73
priority	rc_settings
seq64::rc settings, 433, 434	seq64::rc_settings, 432
private_bus	read_byte
seq64::user_settings, 603	seq64::midifile, 321
private_instrument	read_byte_array
seq64::user_settings, 603	seq64::midifile, 322
process_events	read_long seq64::midifile, 320
seq64::lash, 240	
progress_bar_colored	read_seq_number
seq64::user_settings, 600, 602	seq64::midifile, 323 read_short
progress_bar_thick	seq64::midifile, 321
seq64::user_settings, 600, 602	read_track_name
progress_color	seq64::midifile, 323
seq64::gui_palette_gtk2, 192	read_varinum
prop_item_size	seq64::midifile, 321
seq64::midifile, 325	record change callback
pulse_length_us	seq64::seqedit, 464
seq64, 62	red
pulses_per_measure	seq64::gui_palette_gtk2, 193
seq64, 64	redo
pulses_to_measurestring	seq64::perfedit, 344
seq64, 56	redo_callback
pulses_to_midi_measures	seq64::seqedit, 464
seq64, 56	redraw
pulses_to_string	seq64::mainwid, 253
seq64, 56	seq64::perfnames, 351
pulses_to_timestring	seq64::seqdata, 448
seq64, 57	seq64::seqevent, 475
push_quantize	seq64::seqmenu, 497
seq64::sequence, 561	seq64::seqroll, 506
push_trigger_undo	seq64::seqtime, 522
seq64::perform, 373	redraw_dirty_sequences
seq64::sequence, 535	seq64::perfnames, 351
push_undo	seq64::perfroll, 412
seq64::sequence, 535	redraw_events
seq64::triggers, 574	seq64::seqroll, 506

redraw_period_ms	s_build_follow_progress
seq64::gui_window_gtk2, 197	seq64, <mark>83</mark>
redraw_progress	s_build_highlight_empty
seq64::perfroll, 412	seq64, <mark>83</mark>
remove	s_build_jack_session
seq64::editable_events, 110	seq64, <mark>83</mark>
seq64::event_list, 131	s_build_jack_support
seq64::sequence, 563	seq64, <mark>83</mark>
seq64::triggers, 576	s_build_lash_support
remove_all	seq64, <mark>83</mark>
seq64::sequence, 564	s_build_midi_vector
remove_marked	seq64, <mark>83</mark>
seq64::event_list, 133	s_build_pause_support
seq64::sequence, 557	seq64, <mark>83</mark>
remove_selected	s_build_solid_grid
seq64::sequence, 557	seq64, <mark>83</mark>
seq64::triggers, 577	s_build_timesig_tempo
render_number	seq64, 83
seq64::seqdata, 450	s_build_use_event_map
render_string	seq64, 83
seq64::gui_drawingarea_gtk2, 182	s_character_mapping
render_string_on_drawable	seq64, <mark>83</mark>
seq64::font, 161	s_global_lash_driver
render_string_on_pixmap	seq64, 83
seq64::gui_drawingarea_gtk2, 182	s_handlesize
replace	seq64, 84
seq64::editable_events, 110	s_help_1a
seq64::keys_perform, 223	seq64, 82
reset	s_help_1b
seq64::mainwid, 253	seq64, 83
seq64::perftime, 423	s_help_2
seq64::seqdata, 448	seq64, 83
seq64::seqevent, 475	s_help_3
seq64::seqkeys, 487	seq64, 83
seq64::seqroll, 506	s_help_4
seq64::seqtime, 522	seq64, 83
seq64::sequence, 559	s_jitter_amount
reset_draw_marker	seq64, 84
seq64::sequence, 559	s_statistics_support
reset_draw_trigger_marker	seq64, 83
seq64::sequence, 559	SEQ64_2BUTTON_PRESS
seq64::triggers, 580	seq64, 52
reset_sequences	SEQ64_3BUTTON_PRESS
seq64::perform, 382	seq64, 53
restart_sysex	SEQ64_BUTTON1_MASK
seq64::event, 123	seq64, 52
restore_playing_state	SEQ64 BUTTON2 MASK
seq64::perform, 386	seq64, 52
RevSlotMap	SEQ64_BUTTON3_MASK
seq64::keys_perform, 222	
reveal_alsa_ports	seq64, 52 SEQ64 BUTTON4 MASK
seq64::rc_settings, 433, 434	
P. A	seq64, 52
s_arg_list	SEQ64_BUTTON5_MASK
seq64, 82	seq64, 52
s_build_chord_generator	SEQ64_BUTTON_PRESS
seq64, 83	seq64, 52
s_build_edit_highlight seq64, 83	SEQ64_BUTTON_RELEASE seq64, 53

SEQ64_CONTROL_MASK	seq64::mainwnd, 268
seq64, <u>52</u>	save_playing_state
SEQ64_DELETE	seq64::perform, 386
seq64, 52	save_user_config
SEQ64_DESTROY	seq64::user_settings, 600
seq64, 52	scale_lfo_change
SEQ64_EVENT_LAST	seq64::Ifownd, 243
seq64, 53	screenset dn
SEQ64 EXPOSE	seq64::keys_perform, 224
seq64, <u>52</u>	screenset_up
SEQ64_HYPER_MASK	seq64::keys_perform, 224
seq64, 52	scroll_hadjust
SEQ64_KEY_PRESS	seq64::gui_drawingarea_gtk2, 185
seq64, 53	seq64::gui_window_gtk2, 197
SEQ64_KEY_RELEASE	scroll_hset
seq64, 53	seq64::gui_drawingarea_gtk2, 186
SEQ64_LOCK_MASK	
	seq64::gui_window_gtk2, 197
seq64, 52	scroll_offset_x
SEQ64_MASK_MAX	seq64::seqroll, 512
seq64, 52	scroll_offset_y
SEQ64_META_MASK	seq64::seqroll, 512
seq64, 52	scroll_vadjust
SEQ64_MOD1_MASK	seq64::gui_drawingarea_gtk2, 186
seq64, 5 2	seq64::gui_window_gtk2, 197
SEQ64_MOD2_MASK	scroll_vset
seq64, <mark>52</mark>	seq64::gui_drawingarea_gtk2, 186
SEQ64_MOD3_MASK	seq64::gui_window_gtk2, 197
seq64, 52	select
SEQ64_MOD4_MASK	seq64::event, 124
seq64, 52	seq64::triggers, 576
SEQ64_MOD5_MASK	select_action
seq64, 52	seq64::seqroll, 513
SEQ64 MOTION NOTIFY	select_action_e
seq64, <u>52</u>	seq64::sequence, 533
SEQ64_NO_MASK	select all
seq64, 52	seq64::event_list, 134
SEQ64_NOTHING	seq64::sequence, 549
seq64, 52	select_all_notes
SEQ64_RELEASE_MASK	seq64::sequence, 549
seq64, 52	select_and_mute_group
SEQ64_SCROLL_DOWN	seq64::perform, 377
seq64, 53	select_event
SEQ64_SCROLL_LEFT	seq64::eventslots, 154
seq64, 53	select events
1 /	seq64::sequence, 548
SEQ64_SCROLL_RIGHT	• •
seq64, 53	select_fg_bg_colors
SEQ64_SCROLL_UP	seq64::mainwid, 255
seq64, 53	select_group_mute
SEQ64_SCROLL	seq64::perform, 377
seq64, 53	select_note_events
SEQ64_SHIFT_MASK	seq64::sequence, 547
seq64, 52	select_trigger
SEQ64_SUPER_MASK	seq64::sequence, 543
seq64, 52	selected
save_events	seq64::trigger, 570
seq64::editable_events, 108	selected_trigger_end
seq64::eventslots, 154	seq64::sequence, 546
save_file	selected_trigger_start

seq64::sequence, 546	c_scale_harmonic_minor, 54
selecting	c_scale_major, 54
seq64::seqroll, 513	c_scale_major_pentatonic, 54
Seq24PerfInput	c_scale_melodic_minor, 54
seq64::Seq24PerfInput, 441	c_scale_minor, 54
seq64::perfroll, 417	c_scale_minor_pentatonic, 54
seq64::triggers, 581	c_scale_off, 54
Seq24SeqEventInput	c_scale_size, 54
seq64::Seq24SeqEventInput, 443	c_scales_policy, 80
seq64::seqevent, 481	c_scales_text, 81
seq64, 41	c_scales_transpose_dn, 81
adjustment dummy, 74	c_scales_transpose_up, 80
beats_per_minute_from_tempo_us, 61	c_select_all_events, 55
build_details, 67	c_select_all_notes, 55
bussbyte, 51	c_select_even_notes, 55
c_backsequence, 79	c_select_inverse_events, 55
c_bpmtag, 79	c select inverse notes, 55
c_chord_text, 82	c select odd notes, 55
c_compress_pattern, 55	c_status_queue, 84
c_controller_names, 75	c_status_replace, 83
c expand pattern, 55	c status snapshot, 84
c interval text, 82	c_swing_notes, 55
c_key_text, 82	c_tighten_events, 55
c_mainwid_x, 84	c_tighten_notes, 55
c_mainwid_y, 84	c_timesig, 79
c_max_busses, 82	c_transpose, 79
c max instruments, 82	c_transpose_h, 55
c_midi_control_bpm_dn, 80	c_transpose_notes, 55
c_midi_control_bpm_up, 79	c_triggers, 79
c_midi_control_mod_glearn, 80	c_triggers_new, 79
c_midi_control_mod_gmute, 80	choose_ppqn, 73
c_midi_control_mod_queue, 80	clamp, 75
c_midi_control_mod_replace, 80	clock_e, 53
c_midi_control_mod_snapshot, 80	clock_e, 30 clock tick duration bogus, 63
c_midi_control_play_ss, 80	clock_ticks_from_ppqn, 64
c_midi_control_ss_dn, 80	create_lash_driver, 72
c_midi_control_ss_up, 80	DRAW FIN, 54
c midi controls, 80	DRAW NORMAL LINKED, 54
c midi track ctrl, 79	DRAW NOTE OFF, 54
c_midibus, 78	DRAW NOTE ON, 54
c midibus input size, 77	delete lash driver, 72
c_midibus_output_size, 77	delta time us to ticks, 62
c_midibus_sysex_chunk, 77	double_ticks_from_ppqn, 64
c midich, 78	draw type t, 54
c_midiclocks, 79	e_action_draw, 54
c_midictrl, 79	e action grow, 54
c_music_scales, 53	e_action_select, 54
c_musickey, 79	e_clock_mod, 53
c_musicscale, 79	e_clock_off, 53
c_mutegroups, 79	e_clock_pos, 53
c_notes, 79	e_fruity_interaction, 53
c_perf_bp_mes, 79	e_number_of_interactions, 53
c_perf_bw, 79	e_seq24_interaction, 53
c_quantize_events, 55	EVENT_AFTERTOUCH, 76
c_quantize_notes, 55	EVENT_ANY, 75
c_reserved, 55	EVENT_CHANNEL_PRESSURE, 76
c_scale_blues, 54	EVENT_CLEAR_CHAN_MASK, 77
c_scale_c_whole_tone, 54	EVENT_CONTROL_CHANGE, 76

EVENT_GET_CHAN_MASK, 77	measures_to_ticks, 64
EVENT_MIDI_ACTIVE_SENS, 77	measurestring_to_pulses, 57
EVENT_MIDI_CLOCK, 76	midi_measures_to_pulses, 58
EVENT_MIDI_CONTINUE, 77	midibyte, 51
EVENT_MIDI_META, 77	midilong, 51
EVENT_MIDI_QUARTER_FRAME, 76	midipulse, 51
EVENT_MIDI_RESET, 77	midishort, 51
EVENT_MIDI_SONG_F4, 76	min, 74
EVENT_MIDI_SONG_F5, 76	mouse_action_e, 54
EVENT_MIDI_SONG_F9, 76	output_thread_func, 73
EVENT MIDI SONG FD, 77	parse_command_line_options, 66
EVENT MIDI SONG POS, 76	parse_options_files, 65
EVENT_MIDI_SONG_SELECT, 76	ppqn_is_valid, 69
EVENT MIDI START, 77	pulse_length_us, 62
EVENT MIDI STOP, 77	pulses_per_measure, 64
EVENT MIDI SYSEX CONTINUE, 76	pulses_to_measurestring, 56
EVENT_MIDI_SYSEX_END, 76	pulses_to_midi_measures, 56
EVENT MIDI SYSEX, 76	pulses_to_string, 56
EVENT MIDI TUNE SELECT, 76	pulses_to_timestring, 57
EVENT_NOTE_OFF, 75	rc, 73
EVENT NOTE ON, 76	s_arg_list, 82
EVENT NULL CHANNEL, 77	s_build_chord_generator, 83
EVENT_PITCH_WHEEL, 76	s_build_edit_highlight, 83
EVENT_PROGRAM_CHANGE, 76	s_build_follow_progress, 83
EVENT_STATUS_BIT, 75	s_build_highlight_empty, 83
EVENTS_ALL, 77	s_build_jack_session, 83
EVENTS_UNSELECTED, 77	s_build_jack_support, 83
edit_action_t, 54	s_build_lash_support, 83
extract_timing_numbers, 55	s_build_midi_vector, 83
FF_RW_timeout, 75	s_build_pause_support, 83
file_access, 67	s_build_solid_grid, 83
file_accessible, 68	s_build_timesig_tempo, 83
file_executable, 68	s_build_use_event_map, 83
file_exists, 67	s_character_mapping, 83
file_is_directory, 68	s_global_lash_driver, 83
file_readable, 67	s_handlesize, 84
file_writable, 68	s_help_1a, <mark>82</mark>
font_render, 74	s_help_1b, 83
g_rc_settings, 84	s_help_2, 83
g_user_settings, 84	s_help_3, <mark>83</mark>
gs_mainwid_pointer, 84	s_help_4, 83
gs_perfedit_pointer_0, 84	s_jitter_amount, 84
gs_perfedit_pointer_1, 84	s_statistics_support, 83
help_check, 65	SEQ64_2BUTTON_PRESS, 52
input_thread_func, 73	SEQ64_3BUTTON_PRESS, 53
interaction_method_t, 53	SEQ64_BUTTON1_MASK, 52
jack_process_callback, 71	SEQ64 BUTTON2 MASK, 52
jack_session_callback, 71	SEQ64 BUTTON3 MASK, 52
jack_shutdown_callback, 70	SEQ64_BUTTON4_MASK, 52
jack_sync_callback, 69	SEQ64 BUTTON5 MASK, 52
jack_timebase_callback, 70	SEQ64_BUTTON_PRESS, 52
keyval_name, 71	SEQ64_BUTTON_RELEASE, 53
keyval_normalize, 72	SEQ64_CONTROL_MASK, 52
lash driver, 72	SEQ64 DELETE, 52
log2_time_sig_value, 60	SEQ64 DESTROY, 52
long_options, 82	SEQ64_EVENT_LAST, 53
make directory, 69	SEQ64 EXPOSE, 52
make_section_name, 74	SEQ64 HYPER MASK, 52
	5_40 En_www.ork, 02

SEQ64_KEY_PRESS, 53	m_current_x, 167
SEQ64_KEY_RELEASE, 53	m_current_y, 167
SEQ64_LOCK_MASK, 52	on_button_press_event, 165
SEQ64 MASK MAX, 52	on_button_release_event, 165
SEQ64 META MASK, 52	on_left_button_pressed, 166
SEQ64_MOD1_MASK, 52	on_motion_notify_event, 165
SEQ64_MOD2_MASK, 52	on_right_button_pressed, 166
SEQ64 MOD3 MASK, 52	perfroll, 167
SEQ64_MOD4_MASK, 52	update_mouse_pointer, 166
SEQ64_MOD5_MASK, 52	seq64::FruitySeqEventInput, 167
SEQ64 MOTION NOTIFY, 52	FruitySeqEventInput, 168
SEQ64_NO_MASK, 52	m_is_drag_pasting, 170
SEQ64_NOTHING, 52	m_is_drag_pasting_start, 170
SEQ64_RELEASE_MASK, 52	m_justselected_one, 170
SEQ64_SCROLL_DOWN, 53	on_button_press_event, 169
SEQ64_SCROLL_LEFT, 53	on_button_release_event, 169
SEQ64_SCROLL_RIGHT, 53	on_motion_notify_event, 170
SEQ64_SCROLL_UP, 53	update_mouse_pointer, 168
SEQ64_SCROLL, 53	seq64::FruitySeqRollInput, 170
SEQ64_SHIFT_MASK, 52	FruitySeqRollInput, 171
SEQ64_SUPER_MASK, 52	m_drag_paste_start_pos, 172
seq_event_type_t, 52	m_erase_painting, 172
seq_modifier_t, 51	on_button_press_event, 171
seq_scroll_direction_t, 53	on_button_release_event, 171
shorten_file_spec, 59	on_motion_notify_event, 171
string_is_void, 60	update_mouse_pointer, 171
string_not_void, 59	seq64::Seq24PerfInput, 439
string_to_midibyte, 59	handle_motion_key, 442
string_to_pulses, 58	is_adding, 442
strings_match, 60	m_adding, 442
tempo_to_us, 62	m_effective_tick, 442
tempo_us_from_beats_per_minute, 62	on_button_press_event, 441
tempo_us_to_bytes, 61	on_button_release_event, 441
ticks_to_delta_time_us, 63	on motion notify event, 441
timestring_to_pulses, 58	perfroll, 442
to_string, 67	Seq24PerfInput, 441
update_mainwid_sequences, 75	set_adding, 441
update_perfedit_sequences, 75	seq64::Seq24SeqEventInput, 442
usr, 73	m_adding, 444
versiontext, 82	on_button_press_event, 443
WAVE_INVERSE_TRIANGLE, 51	on button release event, 444
WAVE_INVERSE_TRIANGLE, 51 WAVE_NONE, 51	on motion notify event, 444
WAVE_NONE, 51 WAVE_SINE, 51	Seq24SeqEventInput, 443
	· · · · · · · · · · · · · · · · · · ·
WAVE_STEP, 51	set_adding, 443
WAVE_TRIANGLE, 51	seq64::automutex, 86
wave_func, 65	∼automutex, 87
wave_type_t, 51	automutex, 87
write_options_files, 66	m_safety_mutex, 87
zoom_power_of_2, 61	operator=, 87
seq64::AbstractPerfInput, 85	seq64::click, 88
\sim AbstractPerfInput, 86	button, 90
AbstractPerfInput, 86	click, 89
m_adding_pressed, 86	is_left, 90
on_button_press_event, 86	is_middle, 90
on_button_release_event, 86	is_press, 90
on_motion_notify_event, 86	is_right, 90
seq64::FruityPerfInput, 163	m_button, 90
FruityPerfInput, 165	m_is_press, 90

m_modifier, 90	sm_category_names, 104
m_x, 90	sm_channel_event_names, 104
m_y, 90	sm_meta_event_names, 104
mod_control, 90	sm_prop_event_names, 104
mod_control_shift, 90	sm_system_event_names, 104
mod_super, 90	status_string, 103
modifier, 90	stock_event_string, 103
operator=, 89	time_as_measures, 102
x, 90	time_as_minutes, 102
y, 90	time_as_pulses, 102
seq64::condition_var, 91	timestamp, 102
condition_var, 92	timestamp_format_t, 99
m_cond, 92	timestamp_measures, 100
signal, 92	timestamp_pulses, 100
sm_cond, 92	timestamp_string, 102
wait, 92	timestamp_time, 100
seq64::configfile, 92	value_to_name, 101
\sim configfile, 94	seq64::editable_event::name_value_t, 330
configfile, 94	event_name, 330
line_after, 94	event_value, 330
m d, 95	seq64::editable_events, 105
m_line, 95	~editable events, 108
m name, 95	add, 109, 110
next_data_line, 94	begin, 109
parse, 95	clear, 110
write, 95	const_iterator, 107
seq64::editable_event, 95	count, 109
~editable_event, 100	current_event, 110
analyze, 103	dref, 109
category, 101, 102	editable_events, 107, 108
category_channel_message, 99	end, 109
category meta event, 99	Events, 107
category_name, 99	•
	events, 109 EventsPair, 107
category_prop_event, 99 category_string, 101	eventslots, 110
<u> </u>	
category_system_message, 99	iterator, 107
category_t, 99	Key, 107
channel_string, 103 data string, 103	load_events, 108 m current event, 110
= 0,	,
editable_event, 100	m_events, 110
format_timestamp, 103	m_midi_parameters, 111
m_category, 105	m_sequence, 110
m_format_timestamp, 105	operator=, 108
m_name_category, 105	remove, 110
m_name_channel, 105	replace, 110
m_name_data, 105	save_events, 108
m_name_meta, 105	string_to_pulses, 108
m_name_seqspec, 105	timing, 108
m_name_status, 105	seq64::event, 111
m_name_timestamp, 105	\sim event, 116
m_parent, 105	append_sysex, 122, 123
meta_string, 103	check_channel, 118
name_to_value, 101	clear_link, 123
operator=, 101	data, 124
parent, 101	decrement_data1, 122
seqspec_string, 103	decrement_data2, 122
set_status_from_string, 102	event, 116
sm_category_arrays, 104	get_channel, 118

get_data, 122	seq64::event_list, 127
get_linked, 123	\sim event_list, 130
get_note, 124	add, 131
get_note_velocity, 124	any_selected_notes, 134
get_rank, 125	begin, 130
get_status, 122	clear, 132
get_sysex, 123	clear_links, 133
get_sysex_size, 123	const_iterator, 130
get_timestamp, 118	count, 131
increment_data1, 122	count_selected_events, 134
increment_data2, 122	count_selected_notes, 134
is_channel_msg, 118	dref, 132
is_desired_cc_or_not_cc, 120	editable_events, 134
is_linked, 123	empty, 131
is_marked, 124	end, 130
is_note, 124	event_list, 130
is_note_msg, 119	Events, 130
is_note_off, 124	events, 134
is_note_off_recorded, 125	EventsPair, 130
is_note_on, 124	is_modified, 131
is_one_byte_msg, 118	iterator, 130
is_painted, 123	link_new, 132
is_selected, 124	m_events, 135
is_strict_note_msg, 119	m_is_modified, 135
is_two_byte_msg, 119	mark_all, 133
link, 123	mark_out_of_range, 133
m_channel, 125	mark_selected, 133
m_data, 125	merge, 132
m_has_link, 126	midi_container, 134
m_linked, 126	midi_splitter, 134
m_marked, 126	operator=, 130
m_painted, 126	print, 134
m_selected, 126	remove, 131
m_status, 125	remove_marked, 133
m sysex, 126	select_all, 134
m_sysex_size, 126	sequence, 135
m_timestamp, 125	unmark all, 133
make_clock, 124	unmodify, 131
mark, 123	unpaint_all, 134
mod_timestamp, 120	unselect_all, 134
operator<, 117	verify and link, 133
operator=, 117	seq64::event list::event key, 126
paint, 123	event_key, 126, 127
print, 125	m_rank, 127
restart sysex, 123	m_timestamp, 127
select, 124	operator<, 127
set_channel, 121	seq64::eventedit, 135
set_data, 122	∼eventedit, 140
set_note, 124	change_focus, 142
set_note_velocity, 124	close_out, 143
set_status, 120, 121	enqueue_draw, 140
set_status_keep_channel, 121	eventedit, 139
set_sysex_size, 123	eventslots, 144
set_timestamp, 118	handle cancel, 143
SysexContainer, 116	handle_close, 143
unmark, 123	handle_delete, 143
unpaint, 123	handle insert, 143
unselect, 124	handle modify, 143
a.100.00t, 12.1	nanaio_modify, 170

m botton, 145 m_button_cancel, 145 m_button_isin, 145 m_button_isin, 145 m_button_modify, 145 m_button_modify, 145 m_entry_ev_data_0, 146 m_entry_ev_data_0, 146 m_entry_ev_mame, 146 m_entry_ev_mame, 146 m_entry_ev_mame, 146 m_entry_ev_mame, 146 m_entry_ev_mame, 145 m_label_category, 145 m_label_category, 145 m_label_ev_count, 145 m_label_ev_count, 145 m_label_ising_int, 146 m_sendowox, 145 m_optibox, 145 m_optibox, 145 m_optibox, 145 m_optibox, 145 m_optibox, 146 m_sendowox, 146 m_sendowox, 146 m_showbox, 145 m_optibox, 146 m_sendowox, 146 m_sen		
m_button_calc, 145 m_button_del, 145 m_button_ins, 145 m_button_ins, 145 m_button_save, 145 m_button_save, 145 m_button_save, 145 m_entry_ev_data_0, 146 m_entry_ev_data_1, 146 m_entry_ev_data_1, 146 m_entry_ev_lame, 146 m_entry_ev_lame, 146 m_entry_ev_lame, 145 m_entry_ev_lame, 146 m_entry_ev_lame, 146 m_entry_ev_lame, 145 m_have_focus, 146 m_entry_ev_lame, 145 m_have_focus, 146 m_entry_ev_lame, 145 m_label_category, 145 m_label_channel, 145 m_label_channel, 145 m_label_modified, 145 m_label_modified, 145 m_label_modified, 145 m_label_modified, 145 m_label_modified, 145 m_label_lime_fit, 146 m_label_spacer, 145 m_label_lime_fit, 146 m_label_time_fit, 1	handle_save, 143	delete_current_event, 152
m_button_del, 145 m_button_ins, 145 m_button_modify, 145 m_button_save, 145 m_button_save, 145 m_entry_ev_data_0, 146 m_entry_ev_data_1, 146 m_entry_ev_delta_1, 145 m_entry_ev_delta_1, 146 m_entry_ev_delta_1, 146 m_entry_ev_delta_1, 146 m_entry_ev_delta_1, 146 m_entry_ev_delta_1, 146 m_entry_ev_delta_1, 146 m_entry_ev_delta_1, 145 m_entry_ev_delta_1, 145 m_have_focus, 146 m_have_focus, 145 m_label_edleta_1, 145 m_label_edleta_1, 145 m_label_edleta_1, 145 m_label_edleta_1, 146 m_label_popn, 145 m_label_edleta_1, 146 m_label_edleta_1, 149 m_label_edleta_1, 149 m_label_edleta_1, 140 m_label_edleta_1, 140 m_label_edleta_1, 140 m_label_edleta_1, 140 m_label_edleta_1, 141 mell_edleta_1, 141 mell_edleta_1, 140 m_label_edleta_1, 141 mell_edleta_1, 141 mell_edleta_		
m_button_modify, 145 m_button_modify, 145 m_button_save, 145 m_editbox, 145 m_editbox, 145 m_entry_ev_data_0, 146 m_entry_ev_data_1, 146 m_entry_ev_data_1, 146 m_entry_ev_data_1, 146 m_entry_ev_data_1, 146 m_entry_ev_data_1, 146 m_entry_ev_data_1, 145 m_entry_ev_data_1, 146 m_entry_ev_data_1, 145 m_entry_ev_data_1, 145 m_entry_ev_data_1, 145 m_eventslots, 145 m_have_focus, 146 m_thopbox, 145 m_label_category, 145 m_label_category, 145 m_label_channel, 145 m_label_modified, 145 m_label_modified, 145 m_label_seq_name, 145 m_label_seq_name, 145 m_label_sime_sig, 146 m_label_time_sig, 145 m_label_time_sig, 145 m_otherwork, 145 m_label_time_sig, 145 m_otherwork, 145 m_seq, 146 m_sethowox, 145 m_seq, 146 m_showbox, 145 m_seq, 146 m_solot_sy, 159 m_loution_press_event, 158 on_delet_event, 144 on_focus_oul_event, 144 on_focus_oul_event, 144 on_focus_oul_event, 144 on_focus_oul_event, 158 on_excpose_event, 158 on_botton_press_event, 158 on_horme_down, 158 on_excpose_event, 158 on_frame_down, 158 on_frame_down, 158 on_more_up, 158 on_		- · · · · ·
m_button_modify, 145 m_button_save, 145 m_button_save, 145 m_entry_ev_data_0, 146 m_entry_ev_data_1, 146 m_entry_ev_data_1, 146 m_entry_ev_lata_1, 146 m_entry_ev_lata_1, 146 m_entry_ev_lame, 145 m_entry_ev_lame, 146 m_entry_ev_lame, 145 m_entry_ev_lame, 145 m_entry_ev_lame, 146 m_entry_ev_lame, 145 m_entry_ev_lame, 145 m_entry_ev_lame, 146 m_entry_ev_lame, 145 m_entry_ev_lame, 146 m_entry_ev_lame, 145 m_entry_ev_lame, 146 m_entry_ev_lame, 145 m_entry_ev_lame, 146 m_entry_ev_lame, 145 m_have_focus, 146 m_have_focus, 146 m_have_focus, 146 m_have_focus, 146 m_have_focus, 146 m_label_category, 145 m_label_category, 145 m_label_endoffied, 145 m_label_modified, 145 m_label_pod, 145 m_label_pod, 145 m_label_pod, 145 m_label_seq_name, 145 m_label_seq_name, 145 m_label_seq_name, 145 m_label_seq_name, 145 m_label_time_sig, 145 m_label_time_sig, 145 m_soptbox, 145 m_soltos_vision m_soptbox, 159 m_lop_idex, 159 m_lop_idex, 159 m_lor_idex, 159 m_lop_idex, 159 m_lop_idex, 159 m_lop_idex, 159 m_lor_idex, 159 m_lo		• = -
m_button_save, 145 m_editbox, 145 m_editbox, 145 m_entry_ev_data_0, 146 m_entry_ev_data_1, 146 m_entry_ev_data_1, 146 m_entry_ev_name, 146 m_entry_ev_ev_timestamp, 145 m_eventslots, 145 m_eventslots, 145 m_have_locus, 146 m_label_category, 145 m_label_category, 145 m_label_ev_count, 145 m_label_modified, 145 m_label_modified, 145 m_label_seq_name, 145 m_label_spacer, 145 m_label_spacer, 145 m_label_lime_sig, 145 m_label_time_sig, 145 m_label_time_sig, 145 m_label_time_tim, 146 m_seq, 146 m_showbox, 145 m_label_time_tim, 146 m_label_time_tim, 140 m_label_time_tim, 159 m_lime_count, 159 m_lime_count, 159 m_lime_count, 159 m_lime_count, 159 m_lime_count, 159 m_lime_count, 159 m_lime_time_time_tim, 159 m_lime_count, 159 m_lime_count, 159 m_lime_count, 159 m_lime_count, 159 m_lime_time_time_tim, 159 m_lime_time_time_time_time_time_time_time_t		_ ·
m_editbox, 145 m_entry_ev_data_0, 146 m_entry_ev_data_1, 146 m_entry_ev_data_1, 146 m_entry_ev_data_1, 146 m_entry_ev_data_1, 146 m_entry_ev_data_1, 146 m_entry_ev_limestamp, 145 m_entry_ev_limestamp, 145 m_entry_ev_limestamp, 145 m_eventslots, 145 m_have_focus, 146 m_htopbox, 145 m_labe_focunt, 145 m_label_category, 145 m_label_category, 145 m_label_cy_count, 145 m_label_modified, 145 m_label_poqn, 145 m_label_spacer, 146 m_label_spacer, 145 m_label_spacer, 145 m_label_spacer, 145 m_label_spacer, 145 m_label_time_firt, 146 m_showbox, 145 m_seq, 146 m_showbox, 145 m_table, 144 m_vscroll, 145 m_table, 144 m_vscroll, 145 m_focus_ui_event, 144 on_focus_oui_event, 158 on_gent_oudex, 159 modify_current_event, 158 on_frame_down, 158 on_frame_down, 158 on_frame_down, 158 on_frame_down, 158 on_frame_odown, 158 on_frame_lone, 158 on_move_up, 158 on	m_button_modify, 145	eventedit, 158
m_entry_ev_data_0, 148 m_entry_ev_data_1, 146 m_entry_ev_tata_1, 146 m_entry_ev_tata_1, 146 m_entry_ev_tata_1, 146 m_entry_ev_timestamp, 145 m_eventslots, 145 m_eventslots, 145 m_have_focus, 146 m_htopbox, 145 m_label_category, 145 m_label_category, 145 m_label_category, 145 m_label_ev_count, 145 m_label_poqn, 145 m_label_poqn, 145 m_label_poqn, 145 m_label_seq_name, 145 m_label_space, 145 m_label_space, 145 m_label_time_fmt, 146 m_label_time_fmt, 146 m_label_time_sig, 145 m_seq, 146 m_showbox, 145 m_seq, 146 m_showbox, 145 m_seq, 146 m_showbox, 145 m_label_time_fmt, 146 m_label_time_fmt, 146 m_label_time_fmt, 146 m_label_time_fmt, 146 m_label_time_sig, 145 m_oflotous_in_event, 144 on_focus_in_event, 144 on_focus_out_event, 143 on_ext_focus_out_event, 158 on_letton_rese_event, 158 on_letton_rese_event, 158 on_letton_rese_event, 158 on_letton_rese_event, 158 on_frame_down, 158 on_expose_event, 158 on_frame_home, 158 on_frame_home, 158 on_frame_home, 158 on_frame_home, 158 on_move_oun, 158 on_expose_event, 158 on_move_oun, 158 on_mov	m_button_save, 145	eventslots, 151
m_entry_ev_data_1, 146 m_entry_ev_name, 146 m_entry_ev_name, 146 m_entry_ev_timestamp, 145 m_eventslots, 145 m_have_focus, 146 m_have_focus, 146 m_have_focus, 146 m_have_focus, 146 m_have_focus, 146 m_have_focus, 146 m_have_focus, 145 m_label_category, 145 m_label_category, 145 m_label_category, 145 m_label_category, 145 m_label_modified, 145 m_label_modified, 145 m_label_poqn, 145 m_label_spacer, 146 m_label_spacer, 146 m_label_spacer, 146 m_label_spacer, 146 m_label_spacer, 146 m_label_modified, 145 m_label_spacer, 146	-	increment_bottom, 157
m_entry_ev_iname, 146 m_entry_ev_itimestamp, 145 m_entry_ev_itime_entry_ev_itimestery_event, 158 entry_ev_ev_itime_entry_entry_ev_itime_entry_ev_itime_entry_ev_itime_entry_ev_itime_entry_ev_itime_entry_ev_itime_entry_ev_itime_entry_ev_itime_entry_ev_itime_entry_ev_itime_entry_ev_itime_entry_ev_itime_entry_ev_itime_entry_entry_ev_itime_entry_ev_itime_entry_entry_entry_entry_en	m_entry_ev_data_0, 146	increment_current, 157
m_entry_ev_timestamp, 145 m_eventslots, 145 m_have_focus, 146 m_hlopbox, 145 m_label_category, 145 m_label_category, 145 m_label_category, 145 m_label_category, 145 m_label_category, 145 m_label_category, 145 m_label_modified, 145 m_label_modified, 145 m_label_modified, 145 m_label_spacer, 145 m_label_spacer, 145 m_label_spacer, 145 m_label_time_fimt, 146 m_label_spacer, 145 m_label_time_fimt, 146 m_label_time_fimt, 146 m_label_time_fimt, 146 m_label_time_fimt, 146 m_label_time_fimt, 146 m_label_time_fimt, 145 m_optsbox, 145 m_optsbox, 145 m_seq, 146 m_showbox, 145 m_seq, 158 m_setbox_w, 159 m_barent, 158 m_bottom_reliabe, 144 m_vacroll, 145 on_focus_out_event, 144 on_focus_out_event, 158 on_option_frame_down, 158 on_frame_down, 158 on_frame_pone, 158 on_frame_down, 158 on_frame_pone, 158 on_frame_pone		increment_top, 157
m_eventslots, 145 m have focus, 146 m_htopbox, 145 m_label_category, 145 m_label_category, 145 m_label_category, 145 m_label_category, 145 m_label_category, 145 m_label_category, 145 m_label_ev_count, 145 m_label_modified, 145 m_label_podified, 145 m_label_podified, 145 m_label_seq_name, 145 m_label_seq_name, 145 m_label_seq_name, 145 m_label_seq_name, 145 m_label_time_fmt, 146 m_label_time_sig, 145 m_optsbox, 145 m_rightbox, 145 m_seq, 146 m_showbox, 145 m_showbox, 145 m_stabel, 144 m_vscroll, 145 on_focus_in_event, 144 on_focus_out_event, 144 on_focus_out_event, 144 on_realize, 143 on_set_focus, 143 per_modify, 142 set_event_data_0, 141 set_event_data_0, 141 set_event_timestamp, 141 set_seq_count, 142 seq_64::eventslots, 146 ~eventslots, 156 convert_y, 155 current_index, 151 decrement_current, 157 seq_64::event_current, 157 seq_64::fort, 159		insert_event, 152
m_have_focus, 146 m_hlopbox, 145 m_label_category, 145 m_label_category, 145 m_label_ex_ount, 145 m_label_ex_ount, 145 m_label_ex_ount, 145 m_label_ex_ount, 145 m_label_pron, 145 m_label_pron, 145 m_label_pron, 145 m_label_sex_name, 145 m_label_sex_name, 145 m_label_sex_name, 145 m_label_time_sig, 145 m_olabel_time_sig, 145 m_olabel_time_sig, 145 m_rightbox, 145 m_sex_name, 146 m_sex_name, 145 m_rightbox, 145 m_sex_name, 146 m_locus_out_event, 144 on_focus_out_event, 144 on_focus_out_event, 144 on_name, 141 set_event_data_0, 141 set_event	m_entry_ev_timestamp, 145	line_count, 151
m_htopbox, 145 m label_category, 145 m label_category, 145 m label_channel, 145 m label_en_count, 145 m label_modified, 145 m label_modified, 145 m label_ppqn, 145 m label_ppqn, 145 m label_spacer, 146 m label_spacer, 145 m label_spacer, 145 m label_time_fimt, 146 m label_time_fimt, 146 m label_time_fimt, 146 m label_time_sig, 145 m label_time_sig, 145 m seq, 146 m setow_w, 159 m slots_chars, 158 m slots_x, 159 m slots_chars, 158 m slots_chars m seq, 158 m slots_chars m slots_chars m seq, 158 m slots_chars m seq, 158 m slots_chars m slots_chars m seq, 158 m slots_chars m seq, 158 m slots_chars m slots_chars m seq, 158 m slots_chars m slot	m_eventslots, 145	line_increment, 151
m_label_category, 145 m_label_ev_count, 145 m_label_ev_count, 145 m_label_ev_count, 145 m_label_modified, 145 m_label_pon, 145 m_label_pon, 145 m_label_pon, 145 m_label_pon, 145 m_label_seq_name, 145 m_label_seq_name, 145 m_label_spacer, 145 m_label_time_fint, 146 m_label_time_sig, 145 m_optsbox, 145 m_rightbox, 145 m_seq, 146 m_showbox, 145 m_seq, 146 m_showbox, 145 m_vadjust, 144 m_vscroll, 145 on_focus_in_event, 144 on_focus_in_event, 144 on_focus_out_event, 144 on_realize, 143 on_set_focus, 143 per_modify, 142 set_event_data_0, 141 set_event_data_1, 141 set_event_data_1, 141 set_seq_count, 142 set_event_mame, 141 set_seq_time_sig, 141 set_seq_time_	m_have_focus, 146	line_maximum, 151
m_label_channel, 145 m_label_ev_count, 145 m_label_ev_count, 145 m_label_podified, 145 m_label_podi, 145 m_label_podi, 145 m_label_right, 146 m_label_right, 146 m_label_spacer, 145 m_label_spacer, 145 m_label_time_fmt, 146 m_label_time_sig, 145 m_label_time_sig, 145 m_optsbox, 145 m_seq, 146 m_showbox, 145 m_showbox, 145 m_showbox, 145 m_vacjust, 144 m_vacjust, 144 m_vacjust, 144 no_focus_out_event, 144 on_focus_out_event, 144 on_focus_out_event, 144 on_focus_out_event, 144 on_realize, 143 on_set_focus, 143 perf_modify, 142 set_event_data_0, 141 set_event_data_0, 141 set_event_data_0, 141 set_event_data_0, 141 set_event_data_1, 141 set_event_data_0, 14	m_htopbox, 145	load_events, 151
m_label_ev_count, 145 m_label_modified, 145 m_label_modified, 145 m_label_ppqn, 145 m_label_ppqn, 145 m_label_seq_name, 145 m_label_seq_name, 145 m_label_seq_name, 145 m_label_seq_name, 145 m_label_seq_name, 145 m_label_time_fmt, 146 m_label_time_fmt, 146 m_label_time_sig, 145 m_optsbox, 145 m_optsbox, 145 m_rightbox, 145 m_seq, 146 m_setox_w, 159 m_slots_chars, 158 m_seq, 158 m_seq, 158 m_seq, 158 m_sed, 158 m_seq, 158 m_sed, 159 m_olots_chars, 158 m_slots_x, 159 m_slots_chars, 158 m_slots_v, 159 m_slots_chars, 158 m_slots_v, 159 m_slots_chars, 158 m_sed, 159 m_opitextor, 159 m_olots_chars, 158 m_sed, 158 m_sed, 159 m_olots_chars, 158 m_sed, 159 m_sed, 159 m_slots_chars, 158 m_sed, 159 m_sed, 159 m_sed, 159 m_slots_chars, 158 m_sed, 159 m_sed, 159 m_sed, 159 m_sed, 159 m_sed, 159 m_slots_chars, 158 m_sed, 159 m_sed, 158 m_sed, 159 m_sed,	m_label_category, 145	m_bottom_iterator, 159
m_label_modified, 145 m_label_ppqn, 145 m_label_seq_name, 145 m_label_seq_name, 145 m_label_spacer, 145 m_label_time_fmt, 146 m_label_time_sig, 145 m_optsbox, 145 m_seq, 146 m_showbox, 145 m_seq, 146 m_showbox, 145 m_vadjust, 144 m_vadjust, 144 m_vadjust, 144 m_vadjust, 144 on_focus_out_event, 144 on_focus_out_event, 144 on_focus_out_event, 144 on_realize, 143 on_set_docus, 143 per_modify, 142 set_event_data_0, 141 set_event_data_0, 141 set_event_timestamp, 141 set_seq_time_late, 140 v_adjustnent, 142 seq6::eventslots, 146 convert_y, 155 current_index, 151 decrement_bottom, 157 decrement_current, 157 m_label_rime, 145 m_event_count, 159 m_line_count, 159 m_line_maximum, 159 m_line_ount, 158 m_line_ount, 159 m_line_ount, 158 m_line_ount, 159 m_line_ount, 158 m_line_ount, 159 m_line_ount, 158 m_line_ount, 159 m_line_ount, 158 m_line_ount, 159 m_	m_label_channel, 145	m_char_w, 158
m_label_ppqn, 145 m_label_spqtn, 146 m_label_seq_name, 145 m_label_seq_name, 145 m_label_spacer, 145 m_label_time_fmt, 146 m_label_time_fmt, 146 m_label_time_sig, 145 m_label_time_sig, 145 m_optsbox, 145 m_seq, 146 m_showbox, 145 m_seq, 146 m_showbox, 145 m_seq, 146 m_showbox, 145 m_seq, 158 m_setlox_w, 159 m_slots_chars, 158 m_setlox_w, 159 m_slots_x, 159 m_slots_y, 159 m_slots_y, 159 m_slots_y, 159 m_slots_y, 159 m_top_index, 159 m_top_index, 159 m_top_iterator, 159 modify_current_event, 153 on_bet_focus_in_event, 144 on_realize, 143 on_set_focus, 143 on_set_focus, 143 perf_modify, 142 set_dirty, 142 set_event_data_0, 141 set_event_data_0, 141 set_event_data_1, 141 set_event_name, 141 set_event_mame, 141 set_event_mame, 141 set_event_mame, 141 set_seq_count, 141 set_seq_count, 141 set_seq_count, 141 set_seq_count, 140 v_adjustment, 142 seg68::eventslots, 146 ~eventslots, 156 convert_y, 155 current_index, 151 decrement_current, 157 m_line_count, 159 m_line_count, 158 m_line_count, 158 m_line_count, 158 m_line_lount, 159 m_line_count, 159 m_line_ount, 159 m_line_count, 159 m_line_lount, 159 m_line_lount, 159 m_line_count, 159 m_line_count, 159 m_line_lount, 159 m_line_count, 159 m_line_cut, 159 m_line_cut, 159 m_line_cut, 159 m_line_cut, 159 m_line_cut, 159 m_line_cut,	m_label_ev_count, 145	m_current_index, 159
m_label_right, 146 m_label_spacer, 145 m_label_spacer, 145 m_label_spacer, 145 m_label_time_fmt, 146 m_label_time_fmt, 146 m_label_time_sig, 145 m_optsbox, 145 m_rightbox, 145 m_seq, 146 m_showbox, 145 m_showbox, 145 m_showbox, 145 m_vaciput, 144 m_vaciput, 145 on_delete_event, 144 on_focus_in_event, 144 on_focus_out_event, 144 on_realize, 143 on_set_focus, 143 perf_modify, 142 set_event_data_0, 141 set_event_data_1, 141 set_event_data_1, 141 set_seq_count, 142 set_sed_time_sig, 141 set_seq_time_sig, 141 set_seq_count, 142 seq64::eventslots, 156 convert_y, 155 current_index, 151 decrement_current, 157 m_label_time_fmt, 145 m_line_count, 159 m_line_count, 158 m_line_overl, 158 m_line_count, 159 m_line_count, 159 m_line_count, 159 m_line_count, 159 m_line_count, 159 m_line_count, 159 m_line_leverl, 158 m_line_loverl, 159 m_line_loverl, 159 m_line_nexitipn m_line_overl, 159 m_line_loverl, 159 m_loverl, 159 m_loverl, 159 m_loverl, 159 m_loverl,	m_label_modified, 145	m_current_iterator, 159
m_label_seq_name, 145 m_label_spacer, 145 m_label_time_fmt, 146 m_label_time_sig, 145 m_optsbox, 145 m_optsbox, 145 m_rightbox, 145 m_seq, 146 m_showbox, 145 m_vadjust, 144 m_vadjust, 144 m_vscroll, 145 on_delete_event, 144 on_focus_in_event, 144 on_realize, 143 on_set_focus, 143 perf_modify, 142 set_event_category, 141 set_event_data_0, 141 set_event_timestamp, 141 set_seq_cunt, 142 set_esq_bire, 140 v_adjustment, 142 seq64::eventslots, 146 ceventslots, 146 cevent_index cevent_side cevent, 147 on_sin_event, 148 on_focus_out_event, 158 on_frame_lown, 158 on_frame_lown, 158 on_frame_lown, 158 on_frame_lown, 158 on_orealize, 157 on_focus_in_event, 158 on_frame_lown, 158 on_frame_lown, 158 on_frame_lown, 158 on_frame_lown, 158 on_frame_lown, 158 on_frame_lown, 158 on_size_allocate, 158 page_movement, 156 page_index, 151 change_vert, 156 convert_y, 155 current_index, 151 decrement_bottom, 157 decrement_current, 157 seq64::font, 159	m_label_ppqn, 145	m_event_container, 158
m_label_seq_name, 145 m_label_spacer, 145 m_label_time_fmt, 146 m_label_time_sig, 145 m_optsbox, 145 m_optsbox, 145 m_rightbox, 145 m_seq, 146 m_showbox, 145 m_vadjust, 144 m_vadjust, 144 m_vscroll, 145 on_delete_event, 144 on_focus_in_event, 144 on_realize, 143 on_set_focus, 143 perf_modify, 142 set_event_category, 141 set_event_data_0, 141 set_event_timestamp, 141 set_seq_cunt, 142 set_esq_bire, 140 v_adjustment, 142 seq64::eventslots, 146 ceventslots, 146 cevent_index cevent_side cevent, 147 on_sin_event, 148 on_focus_out_event, 158 on_frame_lown, 158 on_frame_lown, 158 on_frame_lown, 158 on_frame_lown, 158 on_orealize, 157 on_focus_in_event, 158 on_frame_lown, 158 on_frame_lown, 158 on_frame_lown, 158 on_frame_lown, 158 on_frame_lown, 158 on_frame_lown, 158 on_size_allocate, 158 page_movement, 156 page_index, 151 change_vert, 156 convert_y, 155 current_index, 151 decrement_bottom, 157 decrement_current, 157 seq64::font, 159		m event count, 159
m_label_spacer, 145 m_label_time_fmt, 146 m_label_time_sig, 145 m_optsbox, 145 m_optsbox, 145 m_req, 158 m_seq, 146 m_showbox, 145 m_seq, 146 m_showbox, 145 m_seq, 146 m_showbox, 145 m_seq, 158 m_sel, 158 m_sel, 158 m_sel, 158 m_selos_w, 159 m_slots_chars, 158 m_slots_y, 159 m_slots_y, 159 m_slots_y, 159 m_top_index, 159 m_top_index, 159 m_top_index, 159 m_top_index, 159 m_top_index, 159 modify_current_event, 158 on_delete_event, 144 on_focus_in_event, 144 on_focus_out_event, 144 on_key_press_event, 144 on_set_focus, 143 perf_modify, 142 set_dirty, 142 set_event_category, 141 set_event_data_0, 141 set_event_data_0, 141 set_event_tame, 141 set_event_timestamp, 141 set_seq_count, 141 set_seq_count, 141 set_seq_count, 141 set_seq_count, 141 set_seq_count, 141 set_seq_count, 141 set_seq_time_sig, 141 set_seq_time_sig, 141 set_seq_time_sig, 141 set_seq_time_laft on_frame_lone, 158 on_realize, 157 on_scroll_event, 158 on_move_up, 158 on_size_allocate, 158 page_movement, 156 page_topper, 156 set_cevent, 154 select_event, 154 select_event, 154 select_event, 154 set_current_event, 151 decrement_bottom, 157 decrement_current, 157 seq64::font, 159	-	
m_label_time_fmt, 146 m_label_time_sig, 145 m_optsbox, 145 m_optsbox, 145 m_seq, 146 m_showbox, 145 m_seq, 146 m_showbox, 145 m_showbox, 145 m_slotle, 144 m_vacroll, 144 m_vscroll, 145 on_delete_event, 144 on_focus_in_event, 144 on_set_focus, 143 on_set_focus, 143 perf_modify, 142 set_event_data_1, 141 set_event_data_0, 141 set_seq_count, 141 set_seq_count, 141 set_seq_count, 141 set_seq_time_sig, 141 set_seq_time_sig, 141 set_seq_event, 142 seq64::event_slots, 156 convert_y, 155 current_index, 151 decrement_bottom, 157 decrement_bottom, 157 decrement_bottom, 157 decrement_bottom, 157 decrement_bottom, 157 decrement_bottom, 159 m_pager_index, 159 m_pager_index, 159 m_pager_index, 159 m_pager_index, 159 m_set_otox_w, 159 m_set_otox_w, 159 m_slots_v, 159 m_set_otox_w, 159 m_set_otox_w, 159 m_set_otox_w, 159 m_slots_v, 159 m_set_otox_w, 169 m_set_otox_w, 159 m_set_otox_w, 169 m_set_otox_w, 159 m_set_otox_w, 169 m_set_otox_w, 168 m_set_otox_w, 169 m_set_otox_w, 168 m_set_otox_w, 168 m_set_otox_w, 168 m_set_otox_w, 169 m_set_otox_w, 168 m_set_otox_w, 169 m_set_otox_w, 169 m_set_ot	-	
m_label_time_sig, 145 m_optsbox, 145 m_rightbox, 145 m_seq, 146 m_seq, 146 m_showbox, 145 m_vadjust, 144 m_vadjust, 144 m_vadjust, 144 m_vacroll, 145 on_focus_in_event, 144 on_focus_out_event, 144 on_realize, 143 on_set_focus, 142 set_event_data_1, 141 set_event_name, 141 set_seq_time_sig, 141 set_seq_time_sig, 141 set_seq_time_sig, 141 set_seq_time_sig, 141 on_seq, 158 m_pager_index, 159 m_parent, 158 m_set, 158 m_set, 158 m_setox_w, 159 m_setox_w, 159 m_slots_x, 159 m_slots_v, 159 m_slots_v, 159 m_slots_v, 159 m_slots_v, 159 m_slots_v, 159 m_slots_v, 159 m_setox_w, 158 m_set, 058 m_set,	·	
m_optsbox, 145 m_rightbox, 145 m_rightbox, 145 m_seq, 146 m_setobox_w, 159 m_slots_chars, 158 m_slots_chars, 158 m_slots_t, 159 m_slots_x, 159 m_slots_y, 159 m_slots_y, 159 m_slots_y, 159 m_slots_y, 159 m_lop_index, 159 m_top_index, 159 modify_current_event, 158 on_button_press_event, 158 on_button_press_event, 158 on_button_press_event, 158 on_button_press_event, 158 on_button_press_event, 158 on_expose_event, 158 on_frame_down, 158 on_frame_down, 158 on_frame_down, 158 on_frame_up, 158 on_frame_up, 158 on_frame_up, 158 on_frame_up, 158 on_frame_up, 158 on_move_down, 158 on_move_up, 158 on_move_up, 158 on_move_up, 158 on_move_up, 158 on_size_allocate, 158 page_movement, 156 v_adjustment, 142 page_movement, 156 page_index, 151 save_events, 154 select_event, 156		
m_rightbox, 145 m_seq, 146 m_showbox, 145 m_showbox, 145 m_table, 144 m_vadjust, 144 m_vacroll, 145 on_delete_event, 144 on_focus_in_event, 144 on_realize, 143 on_set_focus, 143 perf_modify, 142 set_event_category, 141 set_event_data_0, 141 set_event_data_0, 141 set_event_mame, 141 set_seq_count, 141 set_seq_count, 141 set_seq_count, 141 set_seq_count, 141 set_seq_time_sig, 141 set_seq_time_sig, 141 set_seq_time_sig, 141 set_seq_time_sig, 141 set_seq_event, 142 set_ount_set_focus, 143 set_seq_time_sig, 141 set_seq_time_sig, 145 set_seq_time_sig, 146 v_adjustment, 142 seq64::event_set seq_time, 156 convert_y, 155 current_index, 151 decrement_bottom, 157 decrement_current, 157 m_slots_v, 159 m_setbox_w, 159 m_slots_chars, 158 m_setbox_w, 159 m_setbox_w, 159 m_slots_chars, 158 m_slots_chars_tos m_slot_slot_s_s_s m_lot_slot_s_s_s m_lot_lot_slot_s_s_s m_lot_lot_lot_slot_s_s_s m_lot_l	-	- -
m_seq, 146 m_showbox, 145 m_table, 144 m_vadjust, 144 m_vadjust, 144 m_vscroll, 145 on_delete_event, 144 on_focus_in_event, 144 on_focus_out_event, 144 on_set_focus, 143 perf_modify, 142 set_event_data_0, 141 set_event_data_1, 141 set_event_timestamp, 141 set_seq_cunt, 141 set_seq_cunt, 141 set_seq_cunt, 141 set_seq_time_sig, 141 set_seq_time_sig, 141 set_seq_event, 142 seq64::eventslots, 146 ~eventslots, 156 convert_y, 155 current_event, 157 om_slots_vx, 159 m_slots_chars, 158 m_slots_chars, 159 m_slots_chars, 158 m_slots_chars m_slot_slots_ned m_top_index_slots m_slot_chars m_slot_slots_ned m_top_index_slots m_slot_slots_ned m_top_index_slots m_slot_slots_ned m_top_index_slots m_slot	_ ·	
m_showbox, 145 m_table, 144 m_vadjust, 144 m_vscroll, 145 m_top_index, 159 m_top_index, 158 m_slots_A, 159 m_slots_A, 159 m_top_index, 158 m_slots_A, 159 m_slots_A, 159 m_slots_A, 159 m_top_index, 158 m_slots_A, 159 m_slots_A, 159 m_top_index, 158 m_slots_A, 159 m_slots_A, 159 m_slots_A, 159 m_slots_A, 159 m_top_index, 158 m_slots_A, 159 m_slots_A, 159 m_slots_A, 159 m_top_index, 151 m_to		_ ·
m_table, 144 m_vadjust, 144 m_vscroll, 145 m_vscroll, 145 m_vscroll, 145 m_top_index, 159 m_top_iterator, 159 m_top_index, 151 m_top_i		:
m_vadjust, 144 m_vscroll, 145 m_vscroll, 145 m_top_index, 159 m_top_index, 159 m_top_iterator, 159 modify_current_event, 153 on_focus_out_event, 144 on_button_press_event, 158 on_key_press_event, 144 on_button_press_event, 158 on_expose_event, 157 on_set_focus, 143 perf_modify, 142 set_dirty, 142 set_event_category, 141 set_event_data_0, 141 set_event_data_0, 141 set_event_data_1, 141 set_event_data_1, 141 set_event_timestamp, 141 set_event_timestamp, 141 set_seq_count, 141 set_seq_count, 141 set_seq_time_sig, 151 change_vert, 156 convert_y, 155 current_index, 151 decrement_bottom, 157 decrement_current, 157 seq64::font, 159		
m_vscroll, 145 on_delete_event, 144 on_focus_in_event, 144 on_focus_out_event, 144 on_focus_out_event, 144 on_focus_out_event, 144 on_focus_out_event, 144 on_focus_out_event, 144 on_button_press_event, 158 on_key_press_event, 144 on_button_press_event, 158 on_loution_press_event, 158 on_expose_event, 157 on_set_focus, 143 perf_modify, 142 set_dirty, 142 set_event_category, 141 set_event_data_0, 141 set_event_data_0, 141 set_event_data_1, 141 set_event_data_1, 141 set_event_timestamp, 141 set_seq_count, 141 set_seq_count, 141 set_seq_count, 141 set_seq_ppqn, 141 set_seq_time_sig, 150 v_adjustment, 142 seq64::eventslots, 146 convert_y, 155 current_index, 151 decrement_bottom, 157 decrement_current, 157 m_top_index, 159 m_top_index, 159 m_top_iterator, 158 n_button_release_event, 158 n_button_release_ev		
on_delete_event, 144 on_focus_in_event, 144 on_focus_out_event, 144 on_focus_out_event, 144 on_focus_out_event, 144 on_key_press_event, 144 on_key_press_event, 144 on_button_press_event, 158 on_realize, 143 on_set_focus, 143 on_set_focus, 143 perf_modify, 142 set_dirty, 142 set_event_data_0, 141 set_event_data_0, 141 set_event_data_1, 141 set_event_timestamp, 141 set_event_timestamp, 141 set_seq_count, 141 set_seq_count, 141 set_seq_time_sig, 141 set_seq_time_sig, 141 set_seq_time_sig, 141 set_seq_time_sig, 141 set_seq_time_tide, 140 v_adjustment, 142 seq64::eventslots, 146 ~eventslots, 156 convert_y, 155 current_index, 151 decrement_bottom, 157 decrement_current, 157 modify_current_event, 158 on_button_press_event, 158 on_button_press_event, 158 on_button_press_event, 158 on_button_press_event, 158 on_button_press_event, 158 on_expose_event, 158 on_focus_in_event, 158 on_focus_out_event, 158 on_focus_in_event, 158 on_focus_in_event, 158 on_frame_down, 158 on_frame_down, 158 on_frame_down, 158 on_frame_event, 158 on_frame_event, 158 on_frame_event, 158 on_frame_event, 158 on_frame_down, 158 on_frame_down, 158 on_frame_down, 158 on_frame_event, 158 on_frame_event, 158 on_frame_down, 158 on_frame_down, 158 on_focus_in_event, 158 on_focus_in_even	_ • ·	— — - -
on_focus_in_event, 144 on_focus_out_event, 144 on_button_press_event, 158 on_key_press_event, 144 on_button_press_event, 158 on_key_press_event, 144 on_button_press_event, 158 on_realize, 143 on_set_focus, 143 on_set_focus, 143 on_focus_in_event, 158 on_focus_in_event, 158 on_focus_out_event, 158 on_focus_out_event, 158 on_focus_out_event, 158 on_frame_down, 158 on_frame_down, 158 on_frame_end, 158 on_frame_end, 158 on_frame_end, 158 on_frame_up, 158 on_frame_u	-	— · —
on_focus_out_event, 144 on_button_press_event, 158 on_key_press_event, 144 on_button_release_event, 158 on_realize, 143 on_set_focus, 143 on_set_focus, 143 on_focus_in_event, 158 on_focus_in_event, 158 on_focus_out_event, 158 on_focus_out_event, 158 on_frame_down, 158 set_event_category, 141 on_frame_end, 158 set_event_data_0, 141 on_frame_home, 158 set_event_data_1, 141 on_frame_up, 158 set_event_name, 141 on_move_down, 158 set_event_timestamp, 141 on_move_up, 158 set_seq_count, 141 on_realize, 157 set_seq_ppqn, 141 on_scroll_event, 158 set_seq_time_sig, 141 on_size_allocate, 158 set_seq_title, 140 v_adjustment, 142 seq64::eventslots, 146 v_eventslots, 151 change_vert, 156 convert_y, 155 current_index, 151 decrement_bottom, 157 decrement_current, 157 set_focus on_button_press_event, 158 on_button_release_event, 158 on_expose_event, 158 on_fcus_out_event, 158 on_frame_down, 158 on_fcus_out_event,		
on_key_press_event, 144 on_button_release_event, 158 on_realize, 143 on_set_focus, 143 perf_modify, 142 set_dirty, 142 set_event_category, 141 set_event_data_0, 141 set_event_data_1, 141 set_event_mame, 141 set_event_timestamp, 141 set_seq_count, 141 set_seq_ppqn, 141 set_seq_time_sig, 141 set_seq_time_sig, 141 set_seq_time_sig, 141 set_seq_event, 158 set_seq_event, 158 set_seq_time_sig, 141 set_seq_time_sig, 146 v_adjustment, 142 seq64::eventslots, 146 page_index, 151 change_vert, 156 convert_y, 155 current_index, 151 decrement_bottom, 157 decrement_current, 157 on_button_release_event, 158 on_expose_event, 158 on_fcus_out_event, 158 on_frame_down, 158 on_frame_down, 158 on_frame_down, 158 on_frame_end, 158 on_frame_end, 158 on_frame_end, 158 on_frame_down, 158 on_fcus_out_event, 158 on_frame_down, 158 on_fcus_out_event, 158 on_frame_down, 158 on_fcus_out_event, 158 on_fcus_		·— — ·
on_realize, 143 on_set_focus, 143 on_set_focus, 143 on_focus_in_event, 158 on_focus_out_event, 158 on_frame_down, 158 on_frame_end, 158 on_frame_end, 158 on_frame_home, 158 on_frame_up, 158 on_frame_up, 158 on_frame_up, 158 on_move_down, 158 set_event_name, 141 on_move_down, 158 on_move_up, 158 on_realize, 157 set_seq_count, 141 on_size_allocate, 158 set_seq_time_sig, 141 on_size_allocate, 158 set_seq_title, 140 page_movement, 156 v_adjustment, 142 page_topper, 156 seq64::eventslots, 146 on_size_allocate, 158 set_seq_title, 140 page_movement, 156 v_adjustment, 142 seq64::eventslots, 151 change_vert, 156 convert_y, 155 current_index, 151 decrement_bottom, 157 decrement_current, 157 seq64::font, 159		_ - _ -
on_set_focus, 143 perf_modify, 142 set_dirty, 142 set_event_category, 141 set_event_data_0, 141 set_event_data_1, 141 set_event_timestamp, 141 set_seq_count, 141 set_seq_ppqn, 141 set_seq_time_sig, 141 set_seq_time_sig, 142 set_eventslots, 146 convert_y, 155 current_index, 151 decrement_current, 157 on_focus_in_event, 158 on_focus_out_event, 158 on_focus_out_event, 158 on_focus_out_event, 158 on_frame_down, 158 on_frame_end, 158 on_frame_end.		
perf_modify, 142 set_dirty, 142 set_event_category, 141 set_event_data_0, 141 set_event_data_1, 141 set_event_timestamp, 141 set_seq_count, 141 set_seq_ppqn, 141 set_seq_time_sig, 141 set_seq_title, 140 v_adjustment, 142 seq_64::event_slots, 151 convert_y, 155 current_index, 151 decrement_current, 157 on_frame_down, 158 on_frame_end, 158 on_frame_frame_end, 158 on_frame_frame_frame_frame_frame_frame_frame_frame_frame_frame_frame_frame_fram		
set_dirty, 142 set_event_category, 141 set_event_data_0, 141 set_event_data_1, 141 set_event_name, 141 set_event_timestamp, 141 set_seq_count, 141 set_seq_count, 141 set_seq_time_sig, 141 set_seq_title, 140 v_adjustment, 142 seq64::eventslots, 146 convert_y, 155 current_index, 151 decrement_current, 157 on_frame_end, 158 on_frame_end.		
set_event_category, 141 set_event_data_0, 141 set_event_data_1, 141 set_event_name, 141 set_event_timestamp, 141 set_seq_count, 141 set_seq_ppqn, 141 set_seq_time_sig, 141 v_adjustment, 142 seq64::eventslots, 156 convert_y, 155 current_index, 151 decrement_current, 157 on_frame_end, 158 on_frame_home, 158 on_frame_home, 158 on_frame_home, 158 on_frame_home, 158 on_frame_end, 158 on_frame_home, 158 on_meaup, 158 on_move_down, 158 on_move_down, 158 on_move_down, 158 on_move_up, 158 on_realize, 157 on_scroll_event, 158 on_realize, 157 on_scroll_event, 158 on_realize, 157 on_scroll_event, 158 on_realize, 157 on_scroll_event, 158 on_move_up, 158 on_mov		
set_event_data_0, 141 set_event_data_1, 141 on_frame_up, 158 set_event_name, 141 on_move_down, 158 set_event_timestamp, 141 set_seq_count, 141 set_seq_ppqn, 141 set_seq_time_sig, 141 set_seq_title, 140 v_adjustment, 142 seq64::eventslots, 146 ~eventslots, 151 convert_y, 155 current_index, 151 decrement_current, 157 on_frame_home, 158 on_frame_home, 158 on_frame_home, 158 on_move_up, 158 on_move	_ ·	
set_event_data_1, 141 set_event_name, 141 set_event_timestamp, 141 set_seq_count, 141 set_seq_ppqn, 141 set_seq_time_sig, 141 set_seq_title, 140 v_adjustment, 142 seq64::eventslots, 146 ~eventslots, 151 convert_y, 155 current_index, 151 decrement_current, 157 set_event_down, 158 on_move_down, 158 on_move_up, 158 on_move_up, 158 on_realize, 157 on_scroll_event, 158 on_size_allocate, 158 page_movement, 156 page_topper, 156 pager_index, 151 save_events, 154 select_event, 154 set_text, 154 top_index, 151 seq64::font, 159		
set_event_name, 141 set_event_timestamp, 141 set_seq_count, 141 set_seq_ppqn, 141 set_seq_time_sig, 141 set_seq_title, 140 v_adjustment, 142 seq64::eventslots, 146 convert_y, 156 convert_y, 155 current_index, 151 decrement_current, 157 on_move_down, 158 on_move_up, 158 on_move_up, 158 on_realize, 157 on_scroll_event, 158 on_size_allocate, 158 page_movement, 156 page_movement, 156 page_topper, 156 pager_index, 151 seve_events, 154 select_event, 154 set_text, 154 top_index, 151 decrement_current, 157 seq64::font, 159		
set_event_timestamp, 141 set_seq_count, 141 set_seq_ppqn, 141 set_seq_time_sig, 141 set_seq_time_sig, 141 set_seq_title, 140 v_adjustment, 142 seq64::eventslots, 146 ceventslots, 151 change_vert, 156 convert_y, 155 current_index, 151 decrement_bottom, 157 decrement_current, 157 on_move_up, 158 on_realize, 157 on_scroll_event, 158 on_size_allocate, 158 page_movement, 156 page_topper, 156 pager_index, 151 save_events, 151 set_event, 154 set_current_event, 151 set_text, 154 top_index, 151 seq64::font, 159		
set_seq_count, 141 set_seq_ppqn, 141 on_scroll_event, 158 set_seq_time_sig, 141 set_seq_title, 140 v_adjustment, 142 seq64::eventslots, 146 veventslots, 151 change_vert, 156 convert_y, 155 current_index, 151 decrement_bottom, 157 decrement_current, 157 on_realize, 157 on_scroll_event, 158 page_allocate, 158 page_movement, 156 page_topper, 156 pager_index, 151 save_events, 154 select_event, 154 select_event, 154 set_current_event, 151 set_text, 154 top_index, 151 seq64::font, 159		
set_seq_ppqn, 141 set_seq_time_sig, 141 set_seq_title, 140 v_adjustment, 142 seq64::eventslots, 146 change_vert, 156 convert_y, 155 current_index, 151 decrement_current, 157 on_scroll_event, 158 on_size_allocate, 158 page_movement, 156 page_topper, 156 pager_index, 151 save_events, 154 select_event, 154 set_current_event, 154 set_text, 154 top_index, 151 seq64::font, 159	· ·	·
set_seq_time_sig, 141 set_seq_title, 140 v_adjustment, 142 seq64::eventslots, 146 ~eventslots, 151 change_vert, 156 convert_y, 155 current_index, 151 decrement_current, 157 on_size_allocate, 158 page_movement, 156 page_topper, 156 pager_index, 151 save_events, 154 select_event, 154 set_text, 154 top_index, 151 seq64::font, 159	_ <u>-</u>	_ :
set_seq_title, 140 page_movement, 156 v_adjustment, 142 page_topper, 156 seq64::eventslots, 146 pager_index, 151 ~eventslots, 151 save_events, 154 change_vert, 156 select_event, 154 convert_y, 155 set_current_event, 151 current_index, 151 set_text, 154 decrement_bottom, 157 top_index, 151 decrement_current, 157 seq64::font, 159		
v_adjustment, 142 page_topper, 156 seq64::eventslots, 146 pager_index, 151 ~eventslots, 151 save_events, 154 change_vert, 156 select_event, 154 convert_y, 155 set_current_event, 151 current_index, 151 set_text, 154 decrement_bottom, 157 top_index, 151 decrement_current, 157 seq64::font, 159		
seq64::eventslots, 146 ~eventslots, 151 change_vert, 156 convert_y, 155 current_index, 151 decrement_bottom, 157 decrement_current, 157 seq64::events, 151 save_events, 154 select_event, 154 set_current_event, 151 set_text, 154 top_index, 151 seq64::font, 159		• • —
~eventslots, 151 save_events, 154 change_vert, 156 select_event, 154 convert_y, 155 set_current_event, 151 current_index, 151 set_text, 154 decrement_bottom, 157 top_index, 151 decrement_current, 157 seq64::font, 159	- •	
change_vert, 156 convert_y, 155 current_index, 151 decrement_bottom, 157 decrement_current, 157 select_event, 154 set_current, 151 set_text, 154 top_index, 151 seq64::font, 159	•	
convert_y, 155 set_current_event, 151 current_index, 151 set_text, 154 decrement_bottom, 157 top_index, 151 decrement_current, 157 seq64::font, 159		
current_index, 151set_text, 154decrement_bottom, 157top_index, 151decrement_current, 157seq64::font, 159	- -	
decrement_bottom, 157 top_index, 151 decrement_current, 157 seq64::font, 159	 :	
decrement_current, 157 seq64::font, 159		- ·
- · · · · · · · · · · · · · · · · · · ·		• —
decrement_top, 150 DLACK_ON_CTAIN, 161	-	•
	deorement_top, 150	BLACK_ON_CTAIN, TOT

BLACK_ON_YELLOW, 161	m_background, 187
BLACK, 161	m_current_x, 187
CYAN_ON_BLACK, 161	m_current_y, 187
char_height, 162	m_drop_x, 187
char_width, 162	m_drop_y, 187
Color, 161	m_foreground, 187
font, 161	m_gc, 186
init, 161	m_hadjust, 187
m_b_on_c_pixmap, 163	m_mainperf, 187
m_b_on_y_pixmap, 163	m_pixmap, 187
m_black_pixmap, 162	m_vadjust, 186
m_c_on_b_pixmap, 163	m_window, 186
m_cell_h, 162	m_window_x, 187
m_cell_w, 162	m_window_y, 187
m_clip_mask, 163	on_realize, 186
m_font_h, 162	operator=, 179
m_font_w, 162	perf, 180
m_offset, 162	render_string, 182
m_padded_h, 162	render_string_on_pixmap, 182
m_pixmap, 162	scroll_hadjust, 185
m_use_new_font, 162	scroll_hset, 186
m_white_pixmap, 162	scroll_vadjust, 186
m_y_on_b_pixmap, 163	scroll_vset, 186
padded_height, 162	set_current_drop_x, 186
render_string_on_drawable, 161	set_current_drop_y, 186
WHITE, 161	set_line, 180
YELLOW_ON_BLACK, 161	window_x, 179
seq64::gui_assistant, 172	window_y, 179
∼gui_assistant, 173	seq64::gui_drawingarea_gtk2::rect, 439
gui_assistant, 173	height, 439
jack_idle_connect, 173	width, 439
keys, 174	x, 439
lash_timeout_connect, 173	y, 439
m_keys_perform, 174	seq64::gui_palette_gtk2, 188
quit, 173	\sim gui_palette_gtk2, 192
seq64::gui_assistant_gtk2, 174	bg_color, 193
∼gui_assistant_gtk2, 175	black, 192
gui_assistant_gtk2, 175	black_key, 193
jack_idle_connect, 175	black_paint, 193
lash_timeout_connect, 175	blue, 193
quit, 175	Color, 191
sm_internal_keys, 176	dark_blue, 192
seq64::gui_drawingarea_gtk2, 176	dark_cyan, 192
~gui_drawingarea_gtk2, 179	dark_green, 192
clear_window, 180	dark_grey, 193
current_x, 180	dark_magenta, 192
current_y, 180	dark_orange, 192
draw_drawable, 185	dark_red, 192
draw_line, 180–182	fg_color, 193
draw_line_on_pixmap, 181	green, 193
draw_normal_rectangle_on_pixmap, 185	grey, 193
draw_rectangle, 183, 184	gui_palette_gtk2, 192
draw_rectangle_on_pixmap, 185	is_inverse, 192
drop_x, 180	light_grey, 193
drop_y, 180	line_color, 192
force_draw, 180	load_inverse_palette, 192
gtk_drawarea_init, 186	m_bg_color, 194
gui_drawingarea_gtk2, 179	m_black, 193

m_blk_key, 194 m_blue. 194 m_blue. 194 m_blue. 194 m_dk_blue, 194 m_dk_cyan, 194 m_dk_cyan, 194 m_dk_cyan, 194 m_dk_cyan, 194 m_dk_cyan, 194 m_dk_magenta, 194 m_dk_cyan, 194 m_grey, 194 m_ls_inverse, 193 m_line_color, 194 m_lr_grey, 194 m_lr_grey, 194 m_lr_grey, 194 m_m_ordise, 194 m_white, 194 m_morabe, 210 m_jack_transport. 212 m_jack_transport state, 212 m_jack_transport state, 212 m_jack_transport, 202 set_beats_per_measure, 202 set_beats_per_measure, 202 set_beats_per_minute, 202 set		
m_blue, 194 m_dk blue, 194 m_dk cyan, 194 m_dk cyan, 194 m_dk cyan, 194 m_dk green, 194 m_dk m_dk green, 194 m_dk magenta, 194 m_dk magenta, 194 m_dk magenta, 194 m_dk magenta, 194 m_fg_color, 194 m_green, 194 m_lt_greel, 194 m_norange, 194 m_norange, 194 m_norange, 194 m_whit_ 195 m_greel, 193 miack_green, 193 m_loack_green, 193 m_loack_green, 194 m_lt_greel, 194 m_whit_green, 194 m_whit_green, 194 m_whit_green, 194 m_whit_green, 194 m_whit_green, 194 m_whit_green, 194 m_lack_green, 194 m_lack_gr	m_blk_key, 194	get_current_jack_position, 211
m_dk_olue, 194 m_dk_cyen, 194 m_dk_green, 194 m_dk_green, 194 m_dk_green, 194 m_dk_green, 194 m_dk_magenta, 194 m_dk_orange, 194 m_dk_orange, 194 m_dk_color, 194 m_green, 194 m_line_color, 194 m_line_color, 194 m_line_color, 194 m_orange, 194 m_orange, 194 m_orange, 194 m_orange, 194 m_orange, 194 m_morange, 195 m_jack_gient, 212 m_jack_gien		-
m_dk_grey, 194 m_dk_grey, 194 m_dk_grey, 194 m_dk_grey, 194 m_dk_magenta, 194 m_dk_grey, 194 m_dk_roange, 194 m_dk_roange, 194 m_dk_red, 194 m_gcolor, 194 m_grey, 194 m_grey, 194 m_is_inverse, 193 m_lit_grey, 194 m_ft_grey, 194 m_f		get_jack_pos, 206
m_dk_green, 194 m_dk_grey, 194 m_dk_magenta, 194 m_dk_magenta, 194 m_dk_crange, 194 m_dk_red, 194 m_dk_color, 194 m_green, 194 m_js_inverse, 193 m_line_color, 194 m_orange, 194 m_orange, 194 m_progress_color, 194 m_morange, 194 m_metals_per_measure, 213 m_leats_per_minute, 213 m_leats_per_minute, 213 m_jack_client_ind_212 m_white, 194 m_white, 194 m_white, 194 m_white, 194 m_white, 194 m_white, 194 m_wellow, 194 m_white, 199 mile_green, 193 progress_color, 192 red, 193 white, 192 white_key, 193 white, 192 white_key, 193 white_paint, 193 yellow, 193 white_paint, 193 yellow, 193 white_green, 194 m_mainperf, 198 m_mainperf, 198 m_mainperf, 198 m_mainperf, 198 m_mainperf, 198 m_mindow_y, 198 on_realized, 197 m_is_realized, 197 m_is_realized, 197 m_is_realized, 197 redraw_period_ms, 198 m_mindow_y, 198 on_realize, 197 scroll_hadjust, 197 scroll_yest, 197 seq64:jack_assistant, 201 client_uuid, 206 dieint_open, 207 client_uuid, 206 dieint_open, 207 client_uuid, 206 dieint_loopen, 207 gle beats_per_measure, 202 gle beats_per_measure, 201	m_dk_blue, 194	get_jack_tick, 206
m_dk_grey, 194 m_dk_magenta, 194 m_dk_orange, 194 m_dk_red, 194 m_gcolor, 194 m_grey, 194 m_grey, 194 m_grey, 194 m_si_merse, 193 m_line color, 194 m_lt_grey, 194 m_orange, 194 m_red, 194 m_orange, 194 m_orange, 194 m_red, 194 m_orange, 194 m_whit_grey, 194 m_mit_grey, 194 m_mit_grey, 194 m_mit_grey, 194 m_beat_width_213 m_beats_per_minute, 213 m_jack_client_name, 212 m_jack_client_nam	m_dk_cyan, 194	get_ppqn, 202
m_dk_magenta, 194 m_dk_orange, 194 m_dk_orange, 194 m_dk_orange, 194 m_dk_orange, 194 m_dc_olor, 194 m_green, 194 m_green, 194 m_is_inverse, 193 m_line_color, 194 m_is_inverse, 193 m_line_color, 194 m_orange, 194 m_orange, 194 m_orange, 194 m_orange, 194 m_morange, 193 m_morange, 194 m_mora	m_dk_green, 194	info_message, 206
m_dk_orange, 194 m_dk_red,194 m_gcolor, 194 m_green, 194 m_green, 194 m_grey, 194 m_is_inverse, 193 m_line, color, 194 m_orange, 194 m_orange, 194 m_is_inverse, 193 m_line, color, 194 m_orange, 194 m_morange, 196 m_morange, 197 postion, 204 m_ack_transport_state, 212 m_jack_transport_state, 202 set_beats_per_minute, 203 set_beats_per_mi	m_dk_grey, 194	init, 202
m_dk_red, 194 m_fg_color, 194 m_fg_color, 194 m_grey, 194 m_grey, 194 m_sever, 193 m_lis_inverse, 193 m_lis_color, 194 m_lt_grey, 194 m_lt_grey, 194 m_lt_grey, 194 m_lt_grey, 194 m_orange, 194 m_orange, 194 m_morange, 206 m_morange, 194 m_morange, 206 morange, 194 m_morange, 206 morange, 194 m_morange, 206 morange, 206 morange, 206 morange, 206 morange, 206 morange, 206 morange, 207 morange, 207 morange, 208 morange, 2	m_dk_magenta, 194	is_master, 201
m_fg_color, 194 m_green, 194 m_green, 194 m_green, 194 m_green, 194 m_si_inverse, 193 m_line_color, 194 m_lt_grey, 194 m_orange, 194 m_orange, 194 m_orange, 194 m_orange, 194 m_orange, 194 m_orange, 194 m_morange, 19	m_dk_orange, 194	is_running, 201
m_gree, 194 m_grey, 194 m_js_inverse, 193 m_line_color, 194 m_ls_inverse, 193 m_line_color, 194 m_lt_grey, 194 m_orange, 194 m_orange, 194 m_orange, 194 m_orange, 194 m_orange, 194 m_morange, 194 m_morange, 194 m_morange, 194 m_morange, 194 m_morange, 194 m_white, 194 m_white, 194 m_whit_paint, 194 m_whit_paint, 194 m_yellow, 194 orange, 193 progress_color, 192 m_iack_lient_ame, 212 m_jack_frame_current, 212 m_jack_frame_last, 212 m_jack_frame_last, 212 m_jack_frame_last, 212 m_jack_frame_last, 212 m_jack_master, 213 m_jack_past, 212 m_jack_pas	m_dk_red, 194	jack_assistant, 201
m_gree, 194 m_grey, 194 m_js_inverse, 193 m_line_color, 194 m_ls_inverse, 193 m_line_color, 194 m_lt_grey, 194 m_orange, 194 m_orange, 194 m_orange, 194 m_orange, 194 m_orange, 194 m_morange, 194 m_morange, 194 m_morange, 194 m_morange, 194 m_morange, 194 m_white, 194 m_white, 194 m_whit_paint, 194 m_whit_paint, 194 m_yellow, 194 orange, 193 progress_color, 192 m_iack_lient_ame, 212 m_jack_frame_current, 212 m_jack_frame_last, 212 m_jack_frame_last, 212 m_jack_frame_last, 212 m_jack_frame_last, 212 m_jack_master, 213 m_jack_past, 212 m_jack_pas	m fg color, 194	jack process callback, 210
m_grey, 194 m_js_inverse, 193 m_ls_inverse, 193 m_ls_color, 194 m_ls_inverse, 193 m_ls_color, 194 m_lt_grey, 194 m_orange, 194 m_progress_color, 194 m_progress_color, 194 m_metal, 194 m_metal, 194 m_white, 194 m_wind, 194 m_white, 194 m_white, 194 m_white, 194 m_white, 194 m_wind, 194 m_wite, 194 m_wite, 194 m_wite, 194 m_wite, 194 m_wite, 195 m_jack_client, 212 m_jack_client, 212 m_jack_client, 212 m_jack_frame_last, 212 m_jack_frame_last, 212 m_jack_parent, 212 m_jack_parent, 212 m_jack_parent, 212 m_jack_parent, 212 m_jack_parent, 212 m_jack_tota, 212 m_jack_tota, 212 m_jack_tota, 212 m_jack_tota, 212 m_jack_transport_state, 212 m_jack_tota, 213 m_jack_transport_state, 202 set_baats_per_measure, 202 set_baats_per_dal, 214 s_dumping, 214 s_int_dota, 214 s_dumping, 214 s_int_dota, 214 s_dumping, 214 s_int_dota, 214 s_dumping, 214 s_int_dota, 215 m_ja	_ -	· — —
m_is_inverse, 193 m_line_color, 194 m_t_grey, 194 m_orange, 194 m_orange, 194 m_progress_color, 194 m_white, 194 m_white, 194 m_white, 194 m_wht_paint, 194 m_yellow, 194 orange, 193 progress_color, 192 red, 193 white, 192 white, 192 white, 193 white, 193 white, 193 white, 193 white, 193 white, 193 m_is_realized, 198 m_mainperf, 198 m_mainperf, 198 m_window_gtk2, 196 is_realized, 197 m_is_realized, 197 perf, 197 quit, 197 redraw_period_ms, 197 scroll_hadjust, 197 scroll_yset, 197 scoll_yset, 197 scoll_tacl_yset coll_yset, 206 client_name, 206 client_open, 207 client_uuid, 206 client_name, 206 client_open, 207 client_uuid, 206 deinit, 203 error_message, 206 client_name, 202 set_beats_width, 202 set_beats_per_measure, 202 set_beats_per_minute, 206 scold-isiack_scratchpad, 213 js_clock_tick, 214 js_dumping, 214 js_init_clock, 214 js_looping, 214 js_looping, 214 js_looping, 214 js_looping, 214	— -	• — —
m_line_color, 194 m_lt_grey, 194 m_lt_grey, 194 m_orange, 194 m_progress_color, 194 m_mred, 194 m_white, 194 m_white, 194 m_wht_paint, 194 m_yellow, 194 orange, 193 progress_color, 192 red, 193 white, 192 white, 4ey, 193 white, 192 white, 4ey, 193 white, 192 white, 4ey, 193 white, 192 m_is_realized, 198 m_mainperf, 198 m_mainperf, 198 m_maindow_x, 198 m_window_x, 197 scroll_hadjust, 197 scroll_hadjust, 197 scroll_set, 197 scroll_vset, 197 scroll_vset, 197 seq64:jack_assistant, 201 client_uoid, 206 client_open, 207 client_uuid, 206 deinit, 203 error_message, 206 get_beat_width, 202 get_beats_per_measure, 202 set_beats_vieth, 201 jack_timesbase_callback, 210 m_beat_width, 213 m_beats_per_minute, 213 m_jack_client_name, 212 m_jack_client_unid,		• — —
m_lt_grey, 194 m_orange, 194 m_orange, 194 m_progress_color, 194 m_red, 194 m_white, 194 m_white, 194 m_whit_paint, 194 m_yellow, 194 orange, 193 m_jack_client_name, 212 m_jack_client_name, 212 m_jack_client_name, 212 m_jack_client_uuid, 212 m_jack_client_uuid, 212 m_jack_client_uuid, 212 m_jack_client_uuid, 212 m_jack_frame_current, 212 m_jack_master, 213 m_jack_master, 213 m_jack_pos, 212 m_jack_master, 213 m_jack_pos, 212 m_jack_running, 212 m_jack_transport_state, 212 m	— — ·	· - · -
m_orange, 194 m_progress_color, 194 m_progress_color, 194 m_white, 194 m_yellow, 194 orange, 193 progress_color, 192 red, 193 white, 192 white, 192 white, 4ey, 193 white, 192 white, 193 white, 193 white, 193 m_jack_parent, 212 m_jack_parent, 212 m_jack_prose, 212 m_jack_prose, 212 m_jack_transport_state, 202 set_beats_per_menute, 202 set_beats_per_menute, 202 set_beats_per_menute, 202 set_beats_per_menute, 202 set_beats_per_menute, 202 set_beats_per_menute, 202 set_beats_per_minute, 202 set_beats_per_minute, 202 set_pont, 203 set_pont, 204 set_pont, 205 set_pont, 206 set_pont, 206 client_pont, 207 client_pont, 206 deinit, 203 error_message, 206 get_beats_per_measure, 202 set_beats_per_measure, 202 set_beats_per_minute, 202 set_pont, 203 set_pont, 203 set_pont, 204 set_pont, 205 set_pont, 206 set_pon		· — —
m_progress_color, 194 m_red, 194 m_red, 194 m_white, 194 m_white, 194 m_whit, ey, 194 m_wht_paint, 194 m_wht_paint, 194 m_yellow, 194 orange, 193 progress_color, 192 red, 193 white, 192 white, 49, 193 white, 192 white, 49, 193 white, 193 white, 203 white, 203 white, 203 white, 203 white, 203 m_jack_master, 213 m_jack_prame, 212 m_jack_prame, 213 m_jack_prame, 212 m_jack_prame, 212 m_jack_prame, 212 m_jack_prame, 212 m_jack		
m_red, 194 m_white, 194 m_yellow, 194 orange, 193 progress_color, 192 red, 193 white, 192 white, key, 193 white, 192 white, key, 193 white, laint, 193 yellow, 193 seq64::gui_window_gtk2, 196 gui_window_gtk2, 196 gui_window_gtk2, 196 gui_window_gtk2, 196 m_redraw_period_ms, 198 m_window_x, 198 m_window_x, 198 m_window_x, 198 m_window_x, 198 m_window_y, 198 on_realize, 197 perf, 197 redraw_period_ms, 197 scroll_hadjust, 197 scroll_hadjust, 197 scroll_hadjust, 197 scroll_vadjust, 197 scroll_vad_vady sudvad, 201 slad, 202 set_beats_par_measure, 202 set_beats_par_minute, 202 set_beats_par_minute, 202 set_beats_par_minute, 202 set_beats_par_scroll_vad, 203 set_par_scroll_vad, 206 client_open, 207 client_vad, 206 deinit, 203 error_message, 206 get_beat_width, 202 get_beats_per_measure, 202		
m_white, 194 m_wht_key, 194 m_wht_key, 194 m_wht_paint, 194 m_yellow, 194 m_yellow, 194 m_yellow, 194 m_yellow, 194 m_yellow, 194 m_yack_frame_current, 212 m_jack_frame_last, 212 m_jack_grame_last, 212 m_jack_grame_grame_last, 212 m_jack_grame_grame_last, 212 m_jack_grame_grame, 213 m_jack_grame_grame, 213 m_jack_grame, 214 m_jack_grame, 212 m_jack_gr	_,	
m_wht_key, 194 m_wht_paint, 194 m_yellow, 194 orange, 193 progress_color, 192 red, 193 white, 193 white, ley, 193 white_paint, 194 m_jack_master, 212 m_jack_parent, 212 m_jack_parent, 212 m_jack_pos, 212 m_jack_pos, 212 m_jack_pos, 212 m_jack_tok, 212 m_jack_transport_state, 202 set_bate_par_neasure, 202 set_bate, 214 js_corrent_tok, 214 js_corrent_tick, 214 js_jack_stopped, 214 js_jack_stopped, 214 js_jack_stopped, 214 js_jack_stopped, 214	_ :	- - ·
m_wht_paint, 194 m_yellow, 194 orange, 193 progress_color, 192 red, 193 white, 192 white, 192 white_key, 193 white_paint, 193 yellow, 193 seq64::gui_window_gtk2, 196 gui_window_gtk2, 196 gui_window_gtk2, 196 gui_window_gtk2, 196 gui_window_gtk2, 196 m_ais_realized, 197 m_is_realized, 198 m_mainperf, 198 m_medraw_period_ms, 198 m_window_y, 198 on_realize, 197 perf, 197 quit, 197 redraw_period_ms, 197 scroll_hadjust, 197 scroll_hadjust, 197 scroll_vset, 197 seq64::jack_assistant, 198 ~jack_assistant, 201 client_open, 207 client_uuid, 206 deinit, 203 error_message, 206 get_beats_per_measure, 202 get_beats_per_measure, 202 get_beats_per_measure, 202 seq_64::jack_scratchpad, 213 js_clock_tick, 214 js_jack_stopped, 214 js_jack_stopped, 214 js_jack_stopped, 214 js_jack_stopped, 214 js_jack_stopped, 214 js_jack_stopped, 214		-
m_yellow, 194 orange, 193 progress_color, 192 red, 193 white, 192 white, 192 white_key, 193 white_paint, 193 yellow, 193 seq64::gui_window_gtk2, 196 gui_window_gtk2, 196 gui_window_gtk2, 196 gui_window_gtk2, 196 m_aich_graint, 201 m_is _ realized, 197 m_is _ realized, 198 m_mainperf, 198 m_medraw_period_ms, 198 m_medraw_period_ms, 198 m_mindow_x, 198 on_realize, 197 perf, 197 quit, 197 redraw_period_ms, 197 scroll_hadjust, 197 scroll_hadjust, 197 scroll_vadjust, 197 seq64::jack_assistant, 201 client_open, 207 client_uuid, 206 deinit, 203 error_message, 206 get_beats_per_measure, 202 get_beats_per_measure, 202 get_beats_per_measure, 202 set_lock_fick, 214 js_looping, 214 js_looping, 214 js_looping, 214	•	-
orange, 193 progress_color, 192 red, 193 white, 192 white, 192 white_key, 193 white_paint, 193 yellow, 193 seq64::gui_window_gtk2, 196 gui_window_gtk2, 196 is_realized, 197 m_is_realized, 198 m_mainperf, 198 m_mindow_x, 198 m_window_y, 198 on_redraw_period_ms, 198 m_window_y, 198 on_realize, 197 perf, 197 quit, 197 redraw_period_ms, 197 scroll_hadjust, 197 scroll_hadjust, 197 scroll_vadjust, 197 scroll_vadjust, 197 seq64::jack_assistant, 201 client_name, 206 client_name, 206 client_name, 206 deinit, 203 error_message, 206 get_beat_width, 202 get_beats_per_measure, 202 in_jack_transport_state, 212 m_jack_transport_state, 202 session_eve, 212 m_jack_transport_state, 202 session_eve, 212 m_jack_transport_state, 202 set_beat_width, 202 set_beat_width, 202 set_beat_width, 202 set_beat_width, 202 get_beats_per_measure, 202 is_looping, 214	'	-
progress_color, 192 red, 193 white, 192 white_key, 193 white_paint, 193 yellow, 193 seq64::gui_window_gtk2, 195 ~gui_window_gtk2, 196 gui_window_gtk2, 196 gui_window_gtk2, 196 m_jack_ransport_state_last, 212 m_jack_transport_state_last, 212 m_jack_transport_state_laster_laster_laster_laster_laster_laster_laster_laster_laster_las		
red, 193 white, 192 white, 192 white, 193 white paint, 193 seq64::gui_window_gtk2, 195 ~gui_window_gtk2, 196 gui_window_gtk2, 196 is_realized, 197 m_is_realized, 198 m_mainperf, 198 m_mindow_x, 198 m_mindow_x, 198 m_window_y, 198 m_window_y, 198 m_window_y, 198 on_realize, 197 perf, 197 quit, 197 redraw_period_ms, 197 set_position, 209 set_position, 208 set_position, 209 set_position, 208 set_position, 209 set_position, 208	•	- -
white, 192 white_key, 193 white_paint, 193 yellow, 193 seq64::gui_window_gtk2, 195		-
white_key, 193 white_paint, 193 white_paint, 193 yellow, 193 seq64::gui_window_gtk2, 195 ~gui_window_gtk2, 196 gui_window_gtk2, 196 is_realized, 197 m_is_realized, 198 m_mainperf, 198 m_redraw_period_ms, 198 m_window_y, 198 on_realize, 197 perf, 197 quit, 197 redraw_period_ms, 198 set_beats_per_minute, 202 set_position, 209 set_position, 208 set_position, 209 set_position, 208 set_position, 209 set_position, 208 set_position, 208		
white_paint, 193 yellow, 193 seq64::gui_window_gtk2, 195		
yellow, 193 seq64::gui_window_gtk2, 195 ~gui_window_gtk2, 196 gui_window_gtk2, 196 gui_window_gtk2, 196 is_realized, 197 m_is_realized, 198 m_redraw_period_ms, 198 m_window_y, 198 on_redize, 197 perf, 197 quit, 197 redraw_period_ms, 197 scroll_hadjust, 197 scroll_vset, 197 scroll_vset, 197 seq64::jack_assistant, 201 client_open, 207 client_uuid, 206 get_beat_width, 202 get_beats_per_measure, 202 seq64::jack_stopped, 214 get_beats_per_measure, 202 seq64::jack_stopped, 214 get_beats_per_measure, 202 seq64::jack_scratchpad, 213 ger_ore_measure, 202 seq64::jack_scratchpad, 214 get_beats_per_measure, 202	_ •	- -
seq64::gui_window_gtk2, 196 m_jsession_ev, 212 ~gui_window_gtk2, 196 m_ppqn, 213 gui_window_gtk2, 196 output, 205 is_realized, 197 parent, 201 m_is_realized, 198 position, 204 m_mainperf, 198 session_event, 203 m_redraw_period_ms, 198 set_beats_width, 202 m_window_x, 198 set_beats_per_measure, 202 m_window_y, 198 set_beats_per_minute, 202 on_realize, 197 set_position, 209 perf, 197 set_position, 209 quit, 197 set_position, 209 scroll_hadjust, 197 show_position, 208 scroll_hset, 197 show_position, 208 scroll_vadjust, 197 sm_status_pairs, 212 scroll_vadjust, 197 start, 203 scroll_vaet, 197 stop, 203 seq64::jack_assistant, 198 sync, 209 ~jack_assistant, 201 tick_multiplier, 206 client_open, 206 teck_stipack_scratchpad, 213 client_open, 207 js_clock_tick, 214 client_open, 207 js_dumping, 214 client_cook, 214 js_jack_stopped, 214 <td></td> <td>- · · -</td>		- · · -
~gui_window_gtk2, 196 gui_window_gtk2, 196 gui_window_gtk2, 196 is_realized, 197 m_is_realized, 198 m_mainperf, 198 m_redraw_period_ms, 198 m_window_x, 198 m_window_y, 198 on_realize, 197 perf, 197 quit, 197 redraw_period_ms, 197 scroll_hadjust, 197 scroll_hadjust, 197 scroll_vset, 197 scroll_vset, 197 seq64::jack_assistant, 198	•	
gui_window_gtk2, 196 is_realized, 197 m_is_realized, 198 m_mainperf, 198 m_redraw_period_ms, 198 m_window_x, 198 m_window_y, 198 on_realize, 197 position, 204 session_event, 203 set_beat_width, 202 set_beats_per_measure, 202 m_window_y, 198 on_realize, 197 perf, 197 quit, 197 quit, 197 redraw_period_ms, 197 scroll_hadjust, 197 scroll_hadjust, 197 scroll_vadjust, 197 scroll_vadjust, 197 seq64::jack_assistant, 198 ~jack_assistant, 201 client_206 client_name, 206 client_name, 206 client_open, 207 client_uuid, 206 deinit, 203 error_message, 206 get_beats_per_measure, 202 is_looping, 214 js_looping, 214 js_looping, 214 js_looping, 214 js_looping, 214 js_looping, 214		
is_realized, 197 m_is_realized, 198 m_mainperf, 198 session_event, 203 m_redraw_period_ms, 198 set_beat_width, 202 m_window_x, 198 set_beats_per_measure, 202 m_window_y, 198 set_beats_per_minute, 202 on_realize, 197 set_jostition, 209 quit, 197 redraw_period_ms, 197 scroll_hadjust, 197 scroll_hadjust, 197 scroll_vadjust, 197 scroll_vadjust, 197 seq64::jack_assistant, 198 ~jack_assistant, 201 client_open, 207 client_uuid, 206 deinit, 203 error_message, 206 get_beats_per_measure, 202 parent, 201 position, 203 set_beat_width, 202 set_beat_set_width, 202 set_beat_set_width, 202 set_beat_width, 202 set_		
m_is_realized, 198 m_mainperf, 198 session_event, 203 m_redraw_period_ms, 198 set_beat_width, 202 m_window_x, 198 set_beats_per_measure, 202 m_window_y, 198 set_beats_per_measure, 202 set_beats_per_minute, 202 on_realize, 197 set_josition, 209 quit, 197 set_position, 209 quit, 197 set_position, 209 set_josition, 200		
m_mainperf, 198 m_redraw_period_ms, 198 m_redraw_period_ms, 198 m_window_x, 198 m_window_y, 198 set_beats_per_measure, 202 m_window_y, 198 set_beats_per_measure, 202 m_window_y, 198 set_beats_per_measure, 202 m_window_y, 198 set_beats_per_measure, 202 set_jeak_running, 206 set_jack_running, 206 set_jack_running, 206 set_popition, 209 set_popition, 208 set_beats_per_measure, 202 set_jack_running, 206 set_jack_running, 206 set_popition, 209 set_popition, 209 set_popition, 208 show_position, 208 show_position, 208 start, 203 start, 203 start, 203 start, 203 start, 203 start, 203 stop, 203 set_beats_pairs, 212 start, 203 start, 203 start, 203 stop, 203 set_beats_pairs, 212 start, 203 star	-	•
m_redraw_period_ms, 198 m_window_x, 198 m_window_y, 198 set_beats_per_measure, 202 m_window_y, 198 set_beats_per_measure, 202 set_beats_per_minute, 200 set_per_minute, 200 set_per_measure, 202 set_per_measure, 202 show_position, 208 set_beat_per_measure, 202 set_per_measure, 202 set_per_measure, 202 set_per_measure, 202 set_per_measure, 202 set_per_measure, 202 set_per_measure, 202		•
m_window_x, 198 m_window_y, 198 set_beats_per_measure, 202 m_window_y, 198 set_beats_per_minute, 202 set_beats_per_measure, 202 set_beats_per_meas	m_mainperf, 198	session_event, 203
m_window_y, 198 on_realize, 197 perf, 197 quit, 197 set_position, 209 quit, 197 set_ppqn, 205 redraw_period_ms, 197 scroll_hadjust, 197 scroll_yadjust, 197 scroll_vadjust, 197 scroll_vest, 197 seq64::jack_assistant, 198 ~jack_assistant, 201 client_name, 206 client_name, 206 client_uuid, 206 deinit, 203 error_message, 206 get_beat_width, 202 get_beats_per_measure, 202 set_position, 209 set_ppqn, 205 show_position, 208 show_position, 208 show_statuses, 207 sm_status_pairs, 212 start, 203 start, 203 stop, 203 sync, 209 tick_multiplier, 206 transport_state, 202 seq64::jack_scratchpad, 213 js_clock_tick, 214 js_dumping, 214 js_jack_stopped, 214 js_jack_stopped, 214 js_jack_stopped, 214 js_jack_stopped, 214 js_looping, 214		set_beat_width, 202
on_realize, 197 perf, 197 set_position, 209 quit, 197 set_popqn, 205 redraw_period_ms, 197 scroll_hadjust, 197 scroll_hset, 197 scroll_vadjust, 198 scroll_vadjust, 198 scroll_vadjust, 198 scroll_vadjust, 198 scroll_vadjust, 197 statt, 203 scroll_vadjust, 198 sync, 209 client_lope, 206 client, 206 client, 206 client_name, 206 client_name, 206 client_name, 206 client_open, 207 client_open, 207 client_uuid, 206 deinit, 203 js_clock_tick, 214 deinit, 203 js_current_tick, 214 deinit, 203 js_dumping, 214 get_beat_width, 202 js_jack_stopped, 214 get_beats_per_measure, 202 js_looping, 214	:	_ - _ - _
perf, 197 quit, 197 set_position, 209 set_ppqn, 205 redraw_period_ms, 197 scroll_hadjust, 197 scroll_hset, 197 scroll_vadjust, 198 scroll_vadjust, 198 scroll_vadjust, 197 start, 203 scroll_vadjust, 198 sync, 209 scroll_vadjust, 198 sync, 209 client_lose, 209 client_ack_assistant, 201 client, 206 client, 206 client_name, 206 client_name, 206 client_open, 207 client_open, 207 client_open, 207 client_uuid, 206 deinit, 203 js_clock_tick, 214 js_current_tick, 214 js_jack_stopped, 214 get_beats_per_measure, 202 js_looping, 214	-	set_beats_per_minute, 202
quit, 197 redraw_period_ms, 197 scroll_hadjust, 197 scroll_hset, 197 scroll_vadjust, 197 scroll_vadjust, 197 scroll_vadjust, 197 scroll_vadjust, 197 scroll_vadjust, 197 scroll_vadjust, 197 start, 203 scroll_vadjust, 197 stop, 203 seq64::jack_assistant, 198 sync, 209 client, 206 client, 206 client_name, 206 client_name, 206 client_open, 207 client_uuid, 206 deinit, 203 error_message, 206 gradeautick_multiplier, 206 transport_state, 202 seq64::jack_scratchpad, 213 js_clock_tick, 214 js_current_tick, 214 js_dumping, 214 get_beat_width, 202 js_init_clock, 214 js_jack_stopped, 214 js_jack_stopped, 214 js_looping, 214	on_realize, 197	
redraw_period_ms, 197 scroll_hadjust, 197 scroll_hset, 197 scroll_vadjust, 197 scroll_vadjust, 197 scroll_vadjust, 197 scroll_vadjust, 197 scroll_vadjust, 197 scroll_vadjust, 197 start, 203 scroll_vadjust, 198 supplied start, 203 scroll_vadjust, 198 supplied start, 203 scroll_vadjust, 198 supplied start, 203 scroll_vadjust, 197 start, 203 scroll_vadjust, 197 start, 203 scroll_vadjust, 203 scroll_vadjust, 197 start, 203 start, 203 stop, 203 stop, 203 stop, 209 tick_multiplier, 206 transport_state, 202 client_name, 206 client_name, 206 scq64::jack_scratchpad, 213 js_clock_tick, 214 client_uuid, 206 js_current_tick, 214 deinit, 203 js_current_tick, 214 js_dumping, 214 get_beat_width, 202 js_jack_stopped, 214 get_beats_per_measure, 202 js_looping, 214	perf, 197	set_position, 209
scroll_hadjust, 197 scroll_hset, 197 scroll_hset, 197 scroll_vadjust, 197 scroll_vadjust, 197 scroll_vadjust, 197 scroll_vadjust, 197 start, 203 scroll_vset, 197 stop, 203 seq64::jack_assistant, 198	quit, 197	set_ppqn, 205
scroll_hset, 197 scroll_vadjust, 197 scroll_vadjust, 197 scroll_veet, 197 seq64::jack_assistant, 198	redraw_period_ms, 197	show_position, 208
scroll_vadjust, 197 scroll_vset, 197 seq64::jack_assistant, 198 sync, 209 seq64::jack_assistant, 201 client, 206 client_name, 206 client_open, 207 client_uuid, 206 deinit, 203 ger_obeat_width, 202 get_beats_per_measure, 202 stop, 203 stop, 203 stop, 203 sync, 209 tick_multiplier, 206 transport_state, 202 seq64::jack_scratchpad, 213 js_clock_tick, 214 js_current_tick, 214 js_dumping, 214 js_init_clock, 214 js_jack_stopped, 214 js_jack_stopped, 214	scroll_hadjust, 197	show_statuses, 207
scroll_vset, 197 seq64::jack_assistant, 198 ~jack_assistant, 201 client, 206 client_name, 206 client_open, 207 client_uuid, 206 deinit, 203 error_message, 206 get_beat_width, 202 get_beat_sortachead, 214 stop, 203 stop, 209 sync, 209 tick_multiplier, 206 transport_state, 202 seq64::jack_scratchpad, 213 js_clock_tick, 214 js_current_tick, 214 js_dumping, 214 js_init_clock, 214 js_jack_stopped, 214 js_looping, 214	scroll_hset, 197	sm_status_pairs, 212
seq64::jack_assistant, 198 ~jack_assistant, 201 client, 206 client_name, 206 client_open, 207 client_uuid, 206 deinit, 203 error_message, 206 get_beat_width, 202 get_beat_sper_measure, 202 sync, 209 tick_multiplier, 206 transport_state, 202 seq64::jack_scratchpad, 213 js_clock_tick, 214 js_current_tick, 214 js_dumping, 214 js_init_clock, 214 js_jack_stopped, 214 js_jack_stopped, 214 js_looping, 214	scroll_vadjust, 197	start, 203
~jack_assistant, 201 tick_multiplier, 206 client, 206 transport_state, 202 client_name, 206 seq64::jack_scratchpad, 213 client_open, 207 js_clock_tick, 214 client_uuid, 206 js_current_tick, 214 deinit, 203 js_dumping, 214 error_message, 206 js_init_clock, 214 get_beat_width, 202 js_jack_stopped, 214 get_beats_per_measure, 202 js_looping, 214	scroll_vset, 197	stop, 203
client, 206 transport_state, 202 client_name, 206 seq64::jack_scratchpad, 213 client_open, 207 js_clock_tick, 214 client_uuid, 206 js_current_tick, 214 deinit, 203 js_dumping, 214 error_message, 206 js_init_clock, 214 get_beat_width, 202 js_jack_stopped, 214 get_beats_per_measure, 202 js_looping, 214	seq64::jack_assistant, 198	sync, 209
client_name, 206 client_open, 207 client_uid, 206 client_uuid, 206 client_uuid, 206 client_uid, 203 client_uid, 203 client_uid, 203 client_uid, 203 client_uid, 204 client_uid, 205 client_uid, 204 client_uid, 206 client_uid, 204 client_uid, 206 client_uid, 204 client_uid, 206 client_uid, 214 client_uid, 204 client_uid, 204 client_uid, 204 client_uid, 204 client_uid, 214 client_uid, 204 client_uid, 204 client_uid, 204 client_uid, 204 client_uid, 204 client_uid, 206 client_uid	∼jack_assistant, 201	tick_multiplier, 206
client_name, 206 client_open, 207 client_uid, 206 client_uuid, 206 client_uuid, 206 client_uid, 203 client_uid, 203 client_uid, 203 client_uid, 203 client_uid, 204 client_uid, 205 client_uid, 204 client_uid, 206 client_uid, 204 client_uid, 206 client_uid, 204 client_uid, 206 client_uid, 214 client_uid, 204 client_uid, 204 client_uid, 204 client_uid, 204 client_uid, 214 client_uid, 204 client_uid, 204 client_uid, 204 client_uid, 204 client_uid, 204 client_uid, 206 client_uid	· —	_ ·
client_open, 207 client_uuid, 206 deinit, 203 error_message, 206 get_beat_width, 202 get_beats_per_measure, 202 js_clock_tick, 214 js_current_tick, 214 js_dumping, 214 js_init_clock, 214 js_jack_stopped, 214 js_looping, 214		
client_uuid, 206 js_current_tick, 214 deinit, 203 js_dumping, 214 error_message, 206 js_init_clock, 214 get_beat_width, 202 js_jack_stopped, 214 get_beats_per_measure, 202 js_looping, 214		
deinit, 203 js_dumping, 214 error_message, 206 js_init_clock, 214 get_beat_width, 202 js_jack_stopped, 214 get_beats_per_measure, 202 js_looping, 214	_ ·	• — —
error_message, 206 js_init_clock, 214 get_beat_width, 202 js_jack_stopped, 214 get_beats_per_measure, 202 js_looping, 214		• — —
get_beat_width, 202 js_jack_stopped, 214 get_beats_per_measure, 202 js_looping, 214		
get_beats_per_measure, 202 js_looping, 214		• — —
· - · · ·		
got_oodto_pot_minute, 202 js_piayback_mode, 214		· - · ·
	90204.0_poi_milato, 202	10_pia/baoi_mode, 217

js_ticks_converted_last, 214	m_key_bpm_dn, 231
js_total_tick, 214	m_key_bpm_up, 231
seq64::jack_status_pair_t, 214	m_key_event_edit, 232
jf_bit, 214	m_key_events, 230
jf_meaning, 214	m_key_events_rev, 231
seq64::keybindentry, 214	m_key_group_learn, 232
events, 215	m_key_group_off, 231
groups, 215	m_key_group_on, 231
keybindentry, 215	m_key_groups, 231
location, 215	m_key_groups_rev, 231
m_key, 216	m_key_keep_queue, 231
m_perf, 216	m_key_pattern_edit, 232
m_slot, 216	m_key_pause, 232
m_type, 216	m_key_queue, 231
on_key_press_event, 216	m_key_replace, 231
options, 216	m_key_screenset_dn, 231
set, 216	m_key_screenset_up, 231
type, 215	m_key_set_playing_screenset, 231
seq64::keys_perform, 217	m_key_show_ui_sequence_key, 230
~keys_perform, 222	m_key_show_ui_sequence_number, 230
at_bpm_dn, 228	m key snapshot 1, 231
at_bpm_up, 228	m_key_snapshot_2, 231
at_event_edit, 230	m_key_start, 232
at_group_learn, 229	m_key_stop, 232
_ -	
at_group_off, 229	options, 230
at_group_on, 229	optionsfile, 230
at_keep_queue, 229	pattern_edit, 225, 226
at_pattern_edit, 230	pause, 225
at_pause, 230	perform, 230
at_queue, 229	queue, 223
at_replace, 228	replace, 223
at_screenset_dn, 229	RevSlotMap, 222
at_screenset_up, 229	screenset_dn, 224
at_set_playing_screenset, 229	screenset_up, 224
at_show_ui_sequence_key, 230	set_all_key_events, 228
at_show_ui_sequence_number, 230	set_all_key_groups, 228
at_snapshot_1, 229	set_key_event, 228
at_snapshot_2, 229	set_key_group, 228
at_start, 230	set_keys, 222
at_stop, 230	set_playing_screenset, 224
bpm_dn, 223	show_ui_sequence_key, 226
bpm_up, 223	show_ui_sequence_number, 226
event_edit, 226	SlotMap, 222
get_key_events, 227	snapshot_1, 224
get_key_events_rev, 227	snapshot_2, 224
get_key_groups, 227	start, 225
get_key_groups_rev, 227	stop, 226
get_keys, 223	seq64::keys_perform_gtk2, 232
group_learn, 225	\sim keys_perform_gtk2, 234
group_off, 225	key_name, 234
group_on, 225	keys_perform_gtk2, 234
keep_queue, 223, 224	set_all_key_events, 234
key_name, 227	set_all_key_groups, 234
keys_perform, 222	seq64::keys_perform_transfer, 234
lookup_keyevent_key, 227	kpt_bpm_dn, 235
lookup_keyevent_seq, 227	kpt_bpm_up, 235
lookup_keygroup_group, 227	kpt_event_edit, 236
lookup_keygroup_key, 227	kpt_group_learn, 235
1 70 1 7	1 — 1 — 1

kpt_group_off, 235	m_value, 244
kpt_group_on, 235	m_wave, 244
kpt_keep_queue, 235	on_focus_out_event, 243
kpt_pattern_edit, 236	scale_lfo_change, 243
kpt_pause, 236	toggle_visible, 243
kpt_queue, 235	seq64::maintime, 244
kpt_replace, 235	\sim maintime, 247
kpt_screenset_dn, 235	idle_progress, 247
kpt_screenset_up, 235	m_bar_width, 247
kpt_set_playing_screenset, 235	m_beat_width, 247
kpt_show_ui_sequence_key, 236	m_box_height, 248
kpt_show_ui_sequence_number, 236	m_box_less_pill, 248
kpt_snapshot_1, 235	m_box_width, 248
kpt_snapshot_2, 235	m_flash_height, 248
kpt_start, 236	m_flash_width, 248
kpt_stop, 236	m flash x, 248
seg64::keystroke, 236	m_pill_width, 248
is, 238	m_ppqn, 248
is delete, 238	m tick, 248
is_letter, 238	maintime, 247
is_press, 238	mainwnd, 247
key, 238	on expose event, 247
keystroke, 237	on_realize, 247
m_is_press, 239	operator=, 247
m_key, 239	seq64::mainwid, 249
m_modifier, 239	~mainwid, 252
mod control, 239	calculate_base_sizes, 255
mod_control_shift, 239	draw_marker_on_sequence, 253
mod_super, 239	draw_nrarker_on_sequence, 255 draw_pixmap_on_window, 253
modifier, 238	draw_pixmap_on_window, 255 draw_sequence_on_pixmap, 254
	draw_sequence_pixmap_on_window, 254
operator=, 237 shift lock, 238	draw_sequences_on_pixmap, 254
- :	
seq64::lash, 239	fill_background_window, 253
handle_config, 241	m_button_down, 258 m last tick x, 258
handle_event, 241	:
init, 240	m_mainwid_border, 258
lash, 240	m_mainwid_spacing, 258
m_client, 241	m_mainwid_x, 258
m_is_lash_supported, 241	m_mainwid_y, 258
m_lash_args, 241	m_mainwnd_cols, 258
m_perform, 241	m_mainwnd_rows, 258
process_events, 240	m_max_sets, 258
set_alsa_client_id, 240	m_moving, 258
start, 240	m_moving_seq, 258
seq64::Ifownd, 241	
	m_old_seq, 258
~lfownd, 243	m_progress_height, 259
Ifownd, 243	m_progress_height, 259 m_screenset, 258
lfownd, 243 m_hbox, 244	m_progress_height, 259 m_screenset, 258 m_screenset_offset, 258
lfownd, 243 m_hbox, 244 m_phase, 244	m_progress_height, 259 m_screenset, 258 m_screenset_offset, 258 m_screenset_slots, 258
lfownd, 243 m_hbox, 244 m_phase, 244 m_range, 244	m_progress_height, 259 m_screenset, 258 m_screenset_offset, 258 m_screenset_slots, 258 m_seqarea_seq_x, 258
Ifownd, 243 m_hbox, 244 m_phase, 244 m_range, 244 m_scale_phase, 244	m_progress_height, 259 m_screenset, 258 m_screenset_offset, 258 m_screenset_slots, 258 m_seqarea_seq_x, 258 m_seqarea_seq_y, 258
Ifownd, 243 m_hbox, 244 m_phase, 244 m_range, 244 m_scale_phase, 244 m_scale_range, 244	m_progress_height, 259 m_screenset, 258 m_screenset_offset, 258 m_screenset_slots, 258 m_seqarea_seq_x, 258 m_seqarea_seq_y, 258 m_seqarea_x, 258
Ifownd, 243 m_hbox, 244 m_phase, 244 m_range, 244 m_scale_phase, 244 m_scale_range, 244 m_scale_speed, 244	m_progress_height, 259 m_screenset, 258 m_screenset_offset, 258 m_screenset_slots, 258 m_seqarea_seq_x, 258 m_seqarea_seq_y, 258 m_seqarea_x, 258 m_seqarea_y, 258 m_seqarea_y, 258
Ifownd, 243 m_hbox, 244 m_phase, 244 m_range, 244 m_scale_phase, 244 m_scale_range, 244 m_scale_speed, 244 m_scale_value, 244	m_progress_height, 259 m_screenset, 258 m_screenset_offset, 258 m_screenset_slots, 258 m_seqarea_seq_x, 258 m_seqarea_seq_y, 258 m_seqarea_x, 258 m_seqarea_y, 258 m_seqarea_y, 258 m_text_size_x, 258
Ifownd, 243 m_hbox, 244 m_phase, 244 m_range, 244 m_scale_phase, 244 m_scale_range, 244 m_scale_speed, 244 m_scale_value, 244 m_scale_wave, 244	m_progress_height, 259 m_screenset, 258 m_screenset_offset, 258 m_screenset_slots, 258 m_seqarea_seq_x, 258 m_seqarea_seq_y, 258 m_seqarea_x, 258 m_seqarea_y, 258 m_seqarea_y, 258 m_text_size_x, 258 m_text_size_y, 258
Ifownd, 243 m_hbox, 244 m_phase, 244 m_range, 244 m_scale_phase, 244 m_scale_range, 244 m_scale_speed, 244 m_scale_value, 244 m_scale_wave, 244 m_seq, 243	m_progress_height, 259 m_screenset, 258 m_screenset_offset, 258 m_screenset_slots, 258 m_seqarea_seq_x, 258 m_seqarea_seq_y, 258 m_seqarea_x, 258 m_seqarea_y, 258 m_seqarea_y, 258 m_text_size_x, 258 m_text_size_y, 258 mainwid, 252
Ifownd, 243 m_hbox, 244 m_phase, 244 m_range, 244 m_scale_phase, 244 m_scale_range, 244 m_scale_speed, 244 m_scale_value, 244 m_scale_wave, 244 m_seq, 243 m_seq, 243 m_seqdata, 244	m_progress_height, 259 m_screenset, 258 m_screenset_offset, 258 m_screenset_slots, 258 m_seqarea_seq_x, 258 m_seqarea_seq_y, 258 m_seqarea_x, 258 m_seqarea_y, 258 m_seqarea_y, 258 m_text_size_x, 258 m_text_size_y, 258 mainwid, 252 mainwnd, 257
Ifownd, 243 m_hbox, 244 m_phase, 244 m_range, 244 m_scale_phase, 244 m_scale_range, 244 m_scale_speed, 244 m_scale_value, 244 m_scale_wave, 244 m_seq, 243	m_progress_height, 259 m_screenset, 258 m_screenset_offset, 258 m_screenset_slots, 258 m_seqarea_seq_x, 258 m_seqarea_seq_y, 258 m_seqarea_x, 258 m_seqarea_y, 258 m_seqarea_y, 258 m_text_size_x, 258 m_text_size_y, 258 mainwid, 252

on_button_release_event, 256	m_perf_edit, 270
on_expose_event, 256	m_perf_edit_2, 270
on_focus_in_event, 257	m_ppqn, 270
on_focus_out_event, 257	m_sigpipe, 270
on_motion_notify_event, 257	m_spinbutton_bpm, 271
on_realize, 255	m_spinbutton_load_offset, 271
redraw, 253	m_spinbutton_ss, 271
reset, 253	m_timeout_connect, 272
select_fg_bg_colors, 255	m_tooltips, 270
seq_from_xy, 255	mainwnd, 264
seq_set_and_edit, 253	new_file, 268
seq_set_and_eventedit, 253	new_open_error_dialog, 268
set_screenset, 252	on_delete_event, 269
timeout, 255	on_grouplearnchange, 269
update_mainwid_sequences, 257	on_key_press_event, 269
update_markers, 254	on_key_release_event, 269
update_sequences_on_window, 253	open_file, 264
valid_sequence, 254	open_performance_edit, 266
seq64::mainwnd, 259	open_performance_edit_2, 266
\sim mainwnd, 264	options_dialog, 267
about_dialog, 267	pause_playing, 266
adj_callback_bpm, 265	ppqn, 265
adj_callback_ss, 265	query_save_changes, 267
choose_file, 269	save_file, 268
edit_callback_notepad, 265	sequence_key, 267
enregister_perfedits, 267	set_image, 265
file_exit, 268	set_song_mute, 267
file_import_dialog, 267	signal_action, 269
file_new, 267	start_playing, 266
file_open, 267	stop_playing, 266
file_save, 267	timer_callback, 265
file save as, 268	toLower, 267
handle signal, 265	toggle playing, 266
install_signal_handlers, 269	update window title, 267
is_save, 269	seq64::mastermidibus, 272
learn_toggle, 266	~mastermidibus, 276
m adjust bpm, 271	clock, 278
m_adjust_load_offset, 271	continue from, 278
m_adjust_ss, 271	dump_midi_input, 279
m_button_learn, 271	filter by channel, 277
m_button_perfedit, 271	flush, 277
m button play, 271	get alsa seq, 276
m_button_stop, 271	get_beats_per_minute, 277
m_call_seq_edit, 272	get_clock, 281
m_call_seq_eventedit, 272	get input, 281
m_entry_notes, 271	get_midi_event, 279
m_image_play, 271	get midi in bus name, 277
m_is_running, 271	get_midi_out_bus_name, 277
m_main_cursor, 271	get_num_in_buses, 276
m main time, 270	get_num_out_buses, 276
m main wid, 270	get_ppqn, 277
m_menu_edit, 270	get_sequence, 279
m_menu_file, 270	init, 276
m menu help, 270	init_clock, 278
m_menu_mode, 272	is_dumping, 279
m_menu_view, 270	is_more_input, 278
m_menubar, 270	m_alsa_seq, 281
m_options, 270	m_beats_per_minute, 282
Π_οριίοπο, 270	m_beats_per_minute, 202

m_bus_announce, 282	size, 286
m_buses_in, 282	song_fill_seq_event, 288
m_buses_in_active, 282	song_fill_seq_trigger, 288
m_buses_in_init, 282	seq64::midi_control, 289
m_buses_out, 281	active, 291
m_buses_out_active, 282	data, 291
m_buses_out_init, 282	in_range, 291
m_dumping_input, 282	inverse_active, 291
m_filter_by_channel, 282	m_active, 291
m_init_clock, 282	m_data, 292
m_init_input, 282	m_inverse_active, 291
m_max_busses, 281	m_max_value, 292
m_mutex, 282	m_min_value, 292
m_num_in_buses, 281	m_status, 292
m_num_out_buses, 281	match, 291
m_num_poll_descriptors, 282	max_value, 291
m_poll_descriptors, 282	midi_control, 290
m_ppqn, 282	min_value, 291
m_queue, 282	set, 291
m_seq, 282	status, 291
m_vector_sequence, 282	seq64::midi_list, 292
mastermidibus, 275	\sim midi_list, 294
play, 280	CharList, 294
poll_for_midi, 278	clear, 295
port_exit, 280	done, 294
port_start, 280	get, 295
print, 277	m_char_list, 295
set_beats_per_minute, 276	midi_list, 294
set_clock, 280	put, 295
set_input, 281	size, 294
set_ppqn, 276	seq64::midi_measures, 295
set_sequence_input, 279	beats, 296
start, 277	divisions, 296
stop, 278	m_beats, 297
sysex, 279	m_divisions, 297
seq64::midi_container, 283	m_measures, 297
\sim midi_container, 285	measures, 296
add_event, 287	midi_measures, 296
add_long, 287	seq64::midi_splitter, 297
add_short, 287	\sim midi_splitter, 298
add_variable, 286	count, 299
clear, 286	increment, 299
done, 286	initialize, 299
fill, 285	log_main_sequence, 298
fill_meta_track_end, 288	m_ppqn, 300
fill_proprietary, 288	m_smf0_channels, 300
fill_seq_name, 287	m_smf0_channels_count, 300
fill_seq_number, 287	m_smf0_main_sequence, 300
fill_time_sig_and_tempo, 288	m_smf0_seq_number, 300
get, 286	m_use_default_ppqn, 300
m_position_for_get, 289	midi_splitter, 298
m_sequence, 289	ppqn, 299
midi_container, 285	split, 299
midifile, 289	split_channel, 299
position, 286	seq64::midi_timing, 300
position_increment, 286	beat_width, 302
position_reset, 286	beats_per_measure, 302
put, 286	beats_per_minute, 302

m_beat_width, 303	seq64::midifile, 312
m_beats_per_measure, 303	\sim midifile, 316
m_beats_per_minute, 302	add_trigger, 320
m_ppqn, 303	checklen, 320
midi_timing, 301	errdump, 326
ppqn, 302	error_is_fatal, 317
seq64::midi_vector, 303	error_message, 317
∼midi vector, 305	is_sysex_special_id, 327
CharVector, 305	m_char_list, 328
clear, 306	m data, 328
done, 305	m_disable_reported, 327
get, 306	m_error_is_fatal, 327
m_char_vector, 306	m_error_message, 327
midi vector, 305	m file size, 327
put, 306	m_global_bgsequence, 328
size, 305	
•	m_mutex, 327
seq64::midibus, 306	m_name, 328
∼midibus, 309	m_new_format, 328
clock, 310	m_pos, 327
continue_from, 310	m_ppqn, 328
deinit_in, 309	m_smf0_splitter, 328
flush, 311	m_use_default_ppqn, 328
get_client, 311	midifile, 315
get_clock, 311	parse, 316
get_clock_mod, 311	parse_prop_header, 318
get_id, 310	parse_proprietary_track, 319
get_input, 311	parse_smf_0, 317
get_name, 310	parse_smf_1, 318
get_port, 311	pow2, 320
init_clock, 311	ppqn, 317
init_in, 309	prop_item_size, 325
init_in_sub, 310	read_byte, 321
init_out, 309	read_byte_array, 322
init out sub, 309	read_long, 320
m_clock_mod, 312	read_seq_number, 323
	·_
m_clock_type, 312	read_short, 321
m_dest_addr_client, 312	read_track_name, 323
m_dest_addr_port, 312	read_varinum, 321
m_id, 312	seq_number_size, 327
m_inputing, 312	track_end_size, 327
m_lasttick, 312	track_name_size, 326
m_local_addr_client, 312	varinum_size, 325
m_local_addr_port, 312	write, 317
m_mutex, 312	write_byte, 322
m_name, 312	write_header, 324
m_ppqn, 312	write_long, 321
m_queue, 312	write_prop_header, 324
m_seq, 312	write_proprietary_track, 325
mastermidibus, 311	write_seq_number, 323
midibus, 308, 309	write short, 321
play, 310	write song, 317
print, 310	write track, 327
set clock, 311	write_track_end, 323
set clock mod, 311	write track name, 323
set_input, 311	write_track_name, 323
start, 310	seq64::mutex, 329
	•
stop, 310	lock, 330
sysex, 310	m_mutex_lock, 330

mutex, 330	m_button_bw, 347
sm_recursive_mutex, 330	m_button_collapse, 347
unlock, 330	m_button_copy, 347
seq64::options, 330	m_button_expand, 347
add_jack_sync_page, 333	m_button_grow, 347
add_keyboard_page, 333	m_button_loop, 346
add_midi_clock_page, 333	m_button_play, 346
add_midi_input_page, 333	m_button_redo, 347
add_mouse_page, 333	m_button_snap, 346
button, 332	m_button_stop, 346
clock_callback_mod, 332	m_button_undo, 347
clock_callback_off, 332	m_bw, 347
clock_callback_on, 332	m_entry_bpm, 347
clock_mod_callback, 332	m_entry_bw, 347
e_jack_connect, 332	m_entry_snap, 346
e_jack_disconnect, 332	m_hadjust, 346
e_jack_master, 332	m_hbox, 347
e jack master cond, 332	m hlbox, 347
e_jack_start_mode_live, 332	m_hscroll, 346
e_jack_start_mode_song, 332	m_image_play, 346
e_jack_transport, 332	m is running, 348
filter_callback, 332	m_menu_bpm, 347
input_callback, 332	m menu bw, 347
lash_support_callback, 333	m_menu_snap, 346
m_button_jack_connect, 333	m_peer_perfedit, 346
m_button_jack_disconnect, 333	m_perfnames, 346
m_button_jack_master, 333	m perfroll, 346
m_button_jack_master_cond, 333	m_perfilme, 346
m_button_jack_transport, 333	m_ppqn, 347
m_button_ok, 333	m_snap, 347
m_mainperf, 333	m_standard_bpm, 348
m_notebook, 333	m_table, 346
	m tooltips, 347
m_tooltips, 333	- • •
mouse_fruity_callback, 333	m_vadjust, 346
mouse_mod4_callback, 333	m_vscroll, 346
mouse_seq24_callback, 332	on_delete_event, 345
mouse_snap_split_callback, 333	on_key_press_event, 345
options, 332	on_realize, 345
perf, 332	pause_playing, 345
transport_callback, 332	perfedit, 342
seq64::optionsfile, 334	popup_menu, 344
∼optionsfile, 335	redo, 344
error_message, 337	set_beat_width, 343
optionsfile, 335	set_beats_per_bar, 343
parse, 335	set_guides, 343
write, 336	set_image, 344
seq64::perfedit, 337	set_looped, 344
\sim perfedit, 342	set_snap, 343
collapse, 344	set_zoom, 343
copy, 344	start_playing, 345
draw_sequences, 344	stop_playing, 345
enqueue_draw, 342	timeout, 344
enregister_peer, 343	toggle_playing, 345
expand, 344	undo, 344
grow, 343	update_perfedit_sequences, 345
init_before_show, 342	zoom_check, 342
m_bpm, 347	seq64::perfnames, 348
m_button_bpm, 347	∼perfnames, 350

change_vert, 351	get_key_events, 386
convert_y, 351	get_key_events_rev, 386
draw_sequence, 351	get_key_groups, 386
draw_sequences, 351	get_key_groups_rev, 386
enqueue_draw, 351	get_left_tick, 372
m_char_w, 354	get_max_trigger, 374
m_namebox_w, 355	get_offset, 386
m_names_chars, 354	get_playing_screenset, 377
m_names_x, 355	get_right_tick, 373
m_names_y, 355	get_screen_set_notepad, 375
m_parent, 354	get_screenset, 376
m_seqs_in_set, 355	get_sequence, 381
m_sequence_active, 355	get_start_tick, 372
m_sequence_max, 355	get_tick, 372
m_sequence_offset, 355	gui, 369
m_setbox_w, 355	handle midi control, 375
m xy offset, 355	have_redo, 374
on button press event, 352	have undo, 374
on_button_release_event, 352	highlight, 390
	increment beats per minute, 390
on_expose_event, 352	
on_realize, 352	increment_screenset, 390
on_scroll_event, 354	init_jack, 393
on_size_allocate, 354	inner_start, 396
perfedit, 354	inner_stop, 397
perfnames, 350	input_func, 385
redraw, 351	install_sequence, 396
redraw_dirty_sequences, 351	is_active, 381
seq64::perform, 355	is_control_status, 368
\sim perform, 367	is_dirty_edit, 380
add_sequence, 370	is_dirty_main, 380
all_notes_off, 379	is_dirty_names, 380
any_group_unmutes, 377	is_dirty_perf, 380
clamp_track, 397	is_edit_sequence, 368
clear_all, 370	is_exportable, 381
clear_sequence_triggers, 371	is_group_learning, 378
clocks_per_metronome, 369	is_jack_master, 369
collapse, 374	is_jack_running, 369
copy, 374	is_midi_control_valid, 393
copy_triggers, 373	is_modified, 367, 393
current_screen_set_notepad, 376	is_mseq_valid, 396
decrement beats per minute, 390	is pattern playing, 369, 394
decrement screenset, 390	is_pausable, 369
deinit_jack, 393	is_paused, 369
delete_sequence, 371	is running, 369
enregister, 369	is_screenset_valid, 394
expand, 374	is_seq_valid, 394
FF RW FORWARD, 367	is_sequence_in_edit, 371
FF RW NONE, 367	is_smf_0, 390
FF_RW_REWIND, 367	jack_assistant, 398
ff rw button t, 366	jack_assistant, 398 jack_sync_callback, 398
— — — ·	· — · —
filter_by_channel, 369	key_name, 386
finish, 372	keybindentry, 398
get_32nds_per_quarter, 369	keys, 369
get_beat_width, 368	launch, 370
get_beats_per_bar, 368	launch_input_thread, 392
get_beats_per_minute, 383	launch_output_thread, 393
get_group_mute_state, 385	learn_toggle, 389
get_jack_tick, 372	left_right_size, 373

lookup_keyevent_key, 387	m_starting_tick, 402
lookup_keyevent_seq, 387	m_tick, 402
lookup_keygroup_group, 388	m_tracks_mute_state, 399
lookup_keygroup_key, 387	m_undo_vect, 404
m_32nds_per_quarter, 402	m_us_per_quarter_note, 402
m_beat_width, 401	m_usemidiclock, 403
m_beats_per_bar, 401	m_was_active_edit, 400
m_clocks_per_metronome, 401	m_was_active_main, 400
m_condition_var, 404	m_was_active_names, 400
m_control_status, 403	m_was_active_perf, 400
m_edit_sequence, 404	MUTE_OFF, 366
m_gui_support, 399	MUTE_ON, 366
m_have_redo, 404	MUTE_TOGGLE, 366
m_have_undo, 404	mainwnd_key_event, 391
m in thread, 400	master bus, 369
m in thread launched, 401	max_active_set, 392
m_inputing, 401	midi_control_off, 375
m is modified, 404	midi control on, 375
m_is_pattern_playing, 401	midi control toggle, 374
m_is_paused, 403	midifile, 398
m jack asst, 404	modify, 367
m jack tick, 402	move_triggers, 373
m_left_tick, 402	mute_all_tracks, 384
m_looping, 401	mute_group_offset, 394
m_master_bus, 400	mute_group_tracks, 377
m_max_sets, 403	mute_op_t, 366
m_midi_cc_off, 403	mute_screenset, 384
m_midi_cc_on, 403	new_sequence, 370
m_midi_cc_toggle, 403	off_sequences, 379
m_midiclockpos, 403	options, 398
m midiclockrunning, 403	optionsfile, 398
m_midiclocktick, 403	output_func, 385
m_mode_group, 399	pause_key, 389
m_mode_group_learn, 399	pause_playing, 389
m_mute_group, 399	perform, 367
m_mute_group_selected, 399	perfroll_key_event, 392
m_notify, 404	play, 382
m_offset, 403	playback_key_event, 392
m_one_measure, 402	pop_trigger_redo, 374
m_out_thread, 400	pop_trigger_undo, 373
m_out_thread_launched, 401	position_jack, 379
m_outputing, 401	print_triggers, 372
m_playback_mode, 401	push_trigger_undo, 373
m_playing_screen, 399	reset_sequences, 382
m_playscreen_offset, 399	restore_playing_state, 386
m_ppqn, 401	save_playing_state, 386
m_redo_vect, 404	select_and_mute_group, 377
m_right_tick, 402	select_group_mute, 377
m_running, 401	seq_in_playing_screen, 393
m_screen_set_notepad, 403	sequence_count, 367
m_screenset, 403	sequence_key, 390
m_seqs, 400	sequence_label, 390
m_seqs_active, 400	sequence_max, 367
m_seqs_in_set, 403	sequence_playing_change, 384
m_sequence_count, 403	sequence_playing_off, 384
m_sequence_max, 404	sequence_playing_on, 384
m_sequence_state, 400	sequence_playing_toggle, 383
m_song_start_mode, 399	set_32nds_per_quarter, 369

set_active, 379	convert_xy, 412
set_all_key_events, 397	draw_all, 412
set_all_key_groups, 397	draw_background_on, 413
set_and_copy_mute_group, 378	draw_drawable_row, 413
set_beat_width, 368	draw_progress, 412
set_beats_per_bar, 368	draw_sequence_on, 413
set_beats_per_minute, 382	enqueue_draw, 414
set_edit_sequence, 368	fill_background_pixmap, 411
set_group_mute_state, 385	follow_progress, 412
set_have_redo, 374	FruityPerfInput, 417
set_have_undo, 374	horizontal_adjust, 414
set_input_bus, 391	horizontal_set, 414
set_jack_tick, 372	increment_size, 412
set_key_event, 397	init_before_show, 411
set_key_group, 398	m_4bar_offset, 418
set_left_tick, 372	m_background_x, 418
set_looping, 383	m_beat_length, 418
set_mode_group_learn, 378	m_divs_per_beat, 417
set_mode_group_mute, 377	m_drop_sequence, 419
set_offset, 386	m_drop_tick, 418
set_orig_ticks, 382	m_drop_tick_trigger_offset, 418
set_playback_mode, 394	m_fruity_interaction, 419
set_playing_screenset, 376	m_grow_direction, 419
set_right_tick, 373	m_growing, 419
set_running, 394	m_h_page_increment, 417
set_screen_set_notepad, 376	m_have_button_press, 418
set_screenset, 376	m_measure_length, 418
set_sequence_control_status, 383	m_moving, 419
set_song_mute, 377	m_names_y, 417
set_start_tick, 372	m_old_progress_ticks, 418
set was active, 380	m_page_factor, 417
show_ui_sequence_key, 386	m_parent, 417
show_ui_sequence_number, 387	m_perf_scale_x, 417
sm_mc_dummy, 399	m ppqn, 417
song start mode, 369	m_roll_length_ticks, 418
split_trigger, 374	m seq24 interaction, 419
start, 378	m_sequence_active, 419
start_jack, 379	m_sequence_max, 419
start_key, 389	m_sequence_offset, 418
start_playing, 388	m_size_box_w, 418
stop, 378	m_snap, 417
stop_jack, 379	m_ticks_per_bar, 417
stop_key, 389	m_v_page_increment, 417
stop_playing, 389	m_zoom, 417
toggle all tracks, 384	on button press event, 415
toggle song start mode, 369	on button release event, 415
unset edit sequence, 368	on_expose_event, 415
unset_mode_group_learn, 378	on_focus_in_event, 416
unset_mode_group_mute, 377	on_focus_out_event, 416
unset_sequence_control_status, 383	on_key_press_event, 416
us_per_quarter_note, 369	on_motion_notify_event, 415
seq64::performcallback, 404	on_realize, 414
on_grouplearnchange, 406	on_scroll_event, 416
seq64::perfroll, 406	on size allocate, 416
~perfroil, 411	on_size_request, 416
change_horz, 413	perfedit, 417
change_vert, 413	perfectit, 417
convert_x, 413	redraw_dirty_sequences, 412
CONVENTA, TIO	redraw_dirty_sequences, 412

redraw_progress, 412	filter_by_channel, 433, 434
Seq24PerfInput, 417	help_check, 437
set_guides, 411	home_config_directory, 436
set_ppqn, 412	interaction_method, 433, 435
set_zoom, 414	jack_session_uuid, 433, 435
snap_x, 413	lash_support, 432, 434
split_trigger, 413	last_used_dir, 433, 435
update_sizes, 411	legacy_format, 432, 434
vertical_adjust, 414	m_allow_mod4_mode, 437
vertical_set, 414	m_allow_snap_split, 437
seq64::perftime, 420	m_auto_option_save, 437
\sim perftime, 423	m_config_directory, 438
change_horz, 423	m_config_filename, 438
draw_background, 423	m_config_filename_alt, 438
draw_pixmap_on_window, 425	m_device_ignore, 438
draw_progress_on_window, 423	m_device_ignore_num, 438
enqueue_draw, 423	m_filename, 438
idle_progress, 425	m_filter_by_channel, 438
increment_size, 423	m_interaction_method, 438
key_press_event, 426	m_jack_session_uuid, 438
m_4bar_offset, 426	m_lash_support, 437
m_left_marker_tick, 427	m_last_used_dir, 438
m_measure_length, 427	m_legacy_format, 437
m_parent, 426	m_manual_alsa_ports, 438
m_perf_scale_x, 427	m_pass_sysex, 437
m_ppqn, 427	m_print_keys, 438
m_right_marker_tick, 427	m_priority, 437
m_snap, 427	m_reveal_alsa_ports, 438
m_tick_offset, 426	m_show_midi, 437
m_timearea_y, 427	m_song_start_mode, 438
on_button_press_event, 425	m_stats, 437
on_button_release_event, 426	m user filename, 438
on_expose_event, 425	m_user_filename_alt, 438
on realize, 425	m with jack master, 437
on_size_allocate, 426	m_with_jack_master_cond, 438
perfedit, 426	m with jack transport, 437
perftime, 422	mainwnd, 436
pixel to tick, 424	manual_alsa_ports, 433, 434
reset, 423	operator=, 432
set guides, 423	options, 436
set_ppqn, 424	optionsfile, 436
set_scale, 423	parse_command_line_options, 436
set_zoom, 423	pass_sysex, 433, 434
tick offset, 424	print_keys, 433, 434
tick_to_pixel, 424	priority, 433, 434
update pixmap, 425	rc settings, 432
update_pixmap, 423	reveal alsa ports, 433, 434
seq64::rc_settings, 427	set_config_files, 435
allow_mod4_mode, 432, 434	set_comig_mes, 433
allow_snap_split, 432, 434	show_midi, 433, 434
auto_option_save, 432, 434	song_start_mode, 433, 434
config_directory, 433, 435	stats, 433, 434
config_filename, 433, 435	user_filename, 433, 436
config_filename_alt, 433, 436	user_filename_alt, 434, 436
config_filespec, 432	user_filespec, 432
device_ignore, 433, 434	with_jack, 433
device_ignore_num, 433, 434	with_jack_master, 433, 434
filename, 433, 435	with_jack_master_cond, 433, 434

with_jack_transport, 433, 434	horizontal_set, 462
seq64::rect, 438	m_bgsequence, 468
height, 439	m_button_bpm, 471
width, 439	m_button_bus, 470
x, 439	m_button_bw, 471
y, 439	m_button_channel, 470
seq64::seqdata, 444	m_button_data, 471
~seqdata, 448	m_button_key, 471
change_horz, 449	m_button_length, 471
convert_x, 449	m_button_note_length, 470
draw_events_on, 449	m_button_quantize, 470
draw_events_on_pixmap, 450	m_button_rec_vol, 471
draw_line_on_window, 449	m_button_redo, 470
draw_pixmap_on_window, 450	m_button_scale, 471
idle_redraw, 448	m_button_sequence, 470
Ifownd, 452	m_button_snap, 470
m_cc, 453	m_button_tools, 470
m_dragging, 453	m_button_undo, 470 m_button_zoom, 471
m_number_h, 452 m_number_offset_y, 452	
m number w, 452	m_editing_cc, 471
m numbers, 453	m_editing_status, 471
m_old, 453	m_entry_bpm, 471 m_entry_bus, 470
m_scroll_offset_ticks, 452	m_entry_bw, 471
m_scroll_offset_x, 452	m_entry_channel, 470
m_seq, 452	m_entry_data, 471
m status, 452	m_entry_key, 471
m_zoom, 452	m_entry_length, 471
on_button_press_event, 450	m_entry_name, 471
on_button_release_event, 450	m_entry_note_length, 470
on expose event, 450	m_entry_scale, 471
on_leave_notify_event, 451	m_entry_sequence, 470
on_motion_notify_event, 451	m_entry_snap, 470
on realize, 450	m_entry_zoom, 471
on scroll event, 451	m_hadjust, 469
on_size_allocate, 451	m_have_focus, 472
redraw, 448	m_hbox, 470
render number, 450	m_hbox2, 470
reset, 448	m hscroll new, 469
seqdata, 447	m_initial_note_length, 468
segevent, 452	m initial snap, 468
segroll, 452	m_initial_zoom, 468
set data type, 448	m key, 468
set zoom, 448	m_measures, 468
update pixmap, 448	m_menu_bpm, 469
update_sizes, 448	m_menu_bw, 469
xy_to_rect, 449	m menu data, 469
seq64::seqedit, 453	m_menu_key, 469
∼seqedit, 460	m_menu_length, 469
apply_length, 462	m menu midibus, 469
change focus, 466	m menu midich, 469
create_menu_image, 466	m_menu_note_length, 469
create_menus, 464	m_menu_rec_vol, 469
do_action, 466	m_menu_scale, 469
fill_top_bar, 464	m_menu_sequences, 469
get_measures, 462	m_menu_snap, 469
handle_close, 466	m_menu_tools, 468
horizontal_adjust, 461	m_menu_zoom, 469

m_menubar, 468	update_all_windows, 464
m_note_length, 468	vertical_adjust, 462
m_ppqn, 468	vertical_set, 462
m_scale, 468	seq64::seqevent, 472
m_seq, 468	\sim seqevent, 475
m_seqdata_wid, 469	change_horz, 478
m_seqevent_wid, 470	convert_t, 478
m_seqkeys_wid, 469	convert_x, 478
m_seqroll_wid, 470	draw_background, 476
m_seqtime_wid, 469	draw_events_on, 477
m_snap, 468	draw_events_on_pixmap, 476
m_table, 470	draw_pixmap_on_window, 476
m_toggle_play, 471	draw_selection_on_window, 476
m_toggle_q_rec, 471	drop_event, 477
m_toggle_record, 471	force_draw, 477
m_toggle_thru, 471	FruitySeqEventInput, 481
m_tooltips, 471	idle_redraw, 477
m_vadjust, 469	m cc, 482
m_vbox, 470	m fruity interaction, 481
m_vscroll_new, 469	m_growing, 482
m_zoom, 468	m_move_snap_offset_x, 482
mouse_action, 466	m_moving, 482
name_change_callback, 463	m_moving_init, 482
on_delete_event, 466	m_old, 481
on_focus_in_event, 466	m_painting, 482
on_focus_out_event, 466	m_paste, 482
on_key_press_event, 467	m_ppqn, 481
on_realize, 466	m_scroll_offset_ticks, 481
on_scroll_event, 467	m_scroll_offset_x, 481
on_set_focus, 466	m_selected, 481
play_change_callback, 463	m_selecting, 482
popup_event_menu, 465	m_seq, 481
popup_menu, 465	m_seq24_interaction, 481
popup_midibus_menu, 465	m_seqdata_wid, 481
	m_snap, 481
popup_midich_menu, 465	·
popup_sequence_menu, 465	m_status, 482
popup_tool_menu, 465 q rec change callback, 464	m_zoom, 481
	on_button_press_event, 479
record_change_callback, 464	on_button_release_event, 479
redo_callback, 464	on_expose_event, 479
seqedit, 460	on_focus_in_event, 480
seqmenu, 467	on_focus_out_event, 480
set_background_sequence, 463	on_key_press_event, 480
set_beat_width, 461	on_motion_notify_event, 479
set_beats_per_bar, 461	on_realize, 479
set_data_type, 464	on_size_allocate, 480
set_key, 463	redraw, 475
set_measures, 462	reset, 475
set_midi_bus, 463	Seq24SeqEventInput, 481
set_midi_channel, 463	seqevent, 475
set_note_length, 461	set_data_type, 476
set_rec_vol, 461	set_snap, 476
set_scale, 463	set_zoom, 476
set_snap, 461	snap_x, 478
set_zoom, 460	snap_y, 478
thru_change_callback, 464	start_paste, 477
timeout, 466	update_pixmap, 477
undo_callback, 464	update_sizes, 476

x_to_w, 477	mute_all_tracks, 496
seq64::seqkeys, 482	new_current_sequence, 494
\sim seqkeys, 485	new_sequence, 494
change_vert, 487	on_realize, 497
convert_y, 487	popup_menu, 494
draw_area, 487	redraw, 497
draw_key, 487	seq_clear_perf, 496
force_draw, 486	seq_copy, 495
FruitySeqRollInput, 490	seq_cut, 496
is_black_key, 487	seq_edit, 494
m_hint_key, 490	seq_event_edit, 495
m_hint_state, 490	seq_new, 495
m_key, 490	seq_paste, 496
m_keying, 490	seq_set_and_edit, 495
m_keying_note, 490	seq_set_and_eventedit, 495
m_scale, 490	seqmenu, 493
m_scroll_offset_key, 490	set_bus_and_midi_channel, 496
m_scroll_offset_y, 490	set_edit_sequence, 494
m_seq, 490	set_transposable, 496
m_show_octave_letters, 490	toggle_all_tracks, 496
on_button_press_event, 488	toggle_current_sequence, 494
on_button_release_event, 488	unmute_all_tracks, 496
on_enter_notify_event, 489	unset_edit_sequence, 494
on_expose_event, 488	seq64::seqroll, 497
on_leave_notify_event, 489	∼seqroll, 504
on_motion_notify_event, 489	add_note, 504
on_realize, 488	adding, 513
on_scroll_event, 489	align_selection, 511
on_size_allocate, 489	button_press, 511
reset, 487	button_press_initial, 511
seqkeys, 485	button_release, 511
seqroll, 490	change_horz, 509
set_hint_key, 486	change_vert, 509
set_hint_state, 486	clear_flags, 512
set_key, 486	clear_old, 512
set_listen_button_press, 486	clear_selected, 512
set_listen_button_release, 486	complete_paste, 507
set_listen_motion_notify, 487	convert_sel_box_to_rect, 509
set_scale, 486	convert_tn, 508
update_pixmap, 487	convert_tn_box_to_rect, 508
update_sizes, 487	convert_xy, 508
seq64::seqmenu, 491	draw_background_on_pixmap, 505
∼seqmenu, 494	draw_events_on, 509
current_seq, 494	draw_events_on_pixmap, 505
delete_current_sequence, 494	draw_progress_on_window, 506
get_current_sequence, 494	draw_selection_on_window, 505
get_sequence, 494	drop_action, 513
is_current_seq_active, 494	follow_progress, 507
is_current_seq_in_edit, 494	force_draw, 507
is_edit_sequence, 494	FruitySeqRollInput, 517
is_modified, 494	get_selected_box, 509
m_clipboard, 497	grow_selected_notes, 510
m_current_seq, 497	growing, 513
m_eventedit, 497	horizontal_adjust, 507
m_mainperf, 497	idle_progress, 509
m_menu, 497	idle_redraw, 509
m_modified, 497	m_adding, 518
m_seqedit, 497	m_background_sequence, 519

m_cc, 519	selecting, 513
m_drawing_background_seq, 519	seqedit, 517
m_fruity_interaction, 517	seqroll, 503
m_growing, 518	set_adding, 510
m_horizontal_adjust, 517	set_background_sequence, 505
m_is_drag_pasting, 518	set_current_offset_x_y, 513
m_is_drag_pasting_start, 518	set_data_type, 505
m_justselected_one, 518	set_key, 504
m_key, 518	set_note_length, 504
m_move_delta_x, 518	set_scale, 505
m_move_delta_y, 519	set_snap, 504
m_move_snap_offset_x, 519	set_zoom, 504
m_moving, 518	snap_x, 507
m_moving_init, 518	snap_y, 507
m_note_length, 517	start_paste, 506
m_old, 517	update_and_draw, 506
m_painting, 518	update background, 505
m_paste, 518	update_mouse_pointer, 511
m_pos, 517	update pixmap, 505
m ppqn, 517	update_sizes, 505
m_progress_x, 519	vertical_adjust, 507
m_scale, 517	xy to rect, 508
m_scroll_offset_key, 519	seq64::seqtime, 519
m_scroll_offset_ticks, 519	~seqtime, 521
m_scroll_offset_x, 519	change_horz, 522
	- —
m_scroll_offset_y, 519	draw_pixmap_on_window, 522
m_selected, 517	draw_progress_on_window, 522
m_selecting, 518	idle_progress, 522
m_seq, 517	m_ppqn, 523
m_seqkeys_wid, 517	m_scroll_offset_ticks, 523
m_snap, 517	m_scroll_offset_x, 523
m_status, 519	m_seq, 523
m_vertical_adjust, 517	m_zoom, 523
m_zoom, 517	on_button_press_event, 523
motion_notify, 512	on_button_release_event, 523
move_selected_notes, 510	on_expose_event, 522
move_selection_box, 510	on_realize, 522
moving, 514	on_size_allocate, 523
normal_action, 513	redraw, 522
note_off_length, 504	reset, 522
on_button_press_event, 514	seqtime, 521
on_button_release_event, 514	set_zoom, 522
on_enter_notify_event, 516	update_pixmap, 522
on_expose_event, 514	update_sizes, 522
on_focus_in_event, 515	seq64::sequence, 523
on_focus_out_event, 515	\sim sequence, 534
on_key_press_event, 515	add_event, 541, 553
on_leave_notify_event, 516	add_note, 553
on_motion_notify_event, 514	add_trigger, 542
on_realize, 514	adjust_offset, 563
on_scroll_event, 516	adjust_timestamp, 552
on_size_allocate, 516	adjust_trigger_offsets_to_length, 563
redraw, 506	any_selected_notes, 534
redraw_events, 506	background_sequence, 561
reset, 506	change_event_data_range, 554
scroll_offset_x, 512	channel_match, 564
scroll_offset_y, 512	check_queued_tick, 539
select_action, 513	clear_triggers, 547
	-

clip_timestamp, 552	have_redo, 535
clocks_per_metronome, 536, 537	have_undo, 535
copy_events, 562	increment_selected, 555
copy_selected, 549	intersect_events, 545
copy_selected_trigger, 545	intersect_notes, 544
copy_triggers, 547	intersect_triggers, 544
cut_selected, 550	is_dirty_edit, 540
cut_selected_trigger, 545	is_dirty_main, 540
decrement_selected, 556	is_dirty_names, 540
del_selected_trigger, 545	is_dirty_perf, 540
del_trigger, 543	is_smf_0, 541
e_deselect, 533	link_new, 558
e_is_selected, 533	m_32nds_per_quarter, 567
e_remove_one, 533	m_background_sequence, 568
e_select, 533	m_bus, 565
e_select_one, 533	m_channel_match, 565
e_toggle_selection, 533	m_clocks_per_metronome, 567
e_would_select, 533	m_dirty_edit, 566
event_count, 534	m_dirty_main, 566
event_in_range, 562	m_dirty_names, 566
EventStack, 533	m_dirty_perf, 566
events, 534	m_editing, 566
get_32nds_per_quarter, 537	m_events, 564
get beat width, 536	m_events_clipboard, 564
get_beats_per_bar, 536	m_events_redo, 565
get_clipboard_box, 551	m_events_undo, 565
get_editing, 537	m_events_undo_hold, 565
get_hold_undo, 535	m_have_redo, 565
get_last_tick, 538	m_have_undo, 565
get_length, 538	m_iterator_draw, 565
get_max_trigger, 546	m_last_tick, 566
get_measures, 536	m_length, 567
get_midi_bus, 547	m_masterbus, 565
get_midi_channel, 541	m maxbeats, 566
get_minmax_note_events, 559	m_midi_channel, 565
get_name, 537	m musical key, 568
get next event, 560	m_musical_scale, 568
get_next_note_event, 559	m mutex, 568
get_next_trigger, 560	m_name, 566
get num selected events, 549	m_note_off_margin, 568
get num selected notes, 549	m note off velocity, 567
get playing, 538	m note on velocity, 567
get_ppqn, 536	m notes on, 565
get_quantized_rec, 539	m parent, 564
get_queued, 539	m playing, 566
get_queued_tick, 539	m playing notes, 565
get raise, 537	m ppqn, 566
get_recording, 539	m_quantized_rec, 566
get_selected_box, 551	m_queued, 566
get_song_mute, 537	m_queued_tick, 566
get_thru, 539	m_raise, 566
get_trigger_count, 534	m_rec_vol, 567
get_trigger_offset, 547	m_recording, 566
get_trigger_paste_tick, 534	m_seq_number, 567
get_trigger_state, 543	m_snap_tick, 567
get_triggers, 543	m_song_mute, 565
grow_selected, 556	
-	m_thru, 566
grow_trigger, 543	m_time_beat_width, 567

m_time_beats_per_measure, 567	set_beats_per_bar, 536
m_trigger_offset, 566	set_dirty, 540
m_triggers, 565	set_dirty_mp, 540
m_us_per_quarter_note, 567	set_editing, 537
m_was_playing, 565	set_have_redo, 535
mark_selected, 557	set_have_undo, 535
measures_to_ticks, 536	set_hold_undo, 535
mod_last_tick, 538	set_last_tick, 538
modify, 534	set_length, 537
move_selected_notes, 552	set_master_midi_bus, 547
move_selected_triggers_to, 545	set_measures, 536
move_triggers, 546	set_midi_bus, 547
musical_key, 561	set_midi_channel, 541
musical_scale, 561	set_name, 536
name, 537	set_parent, 562
note_off_margin, 562	set_playing, 538
number, 534	set_quantized_rec, 539
off_playing_notes, 558	set_raise, 537 set_rec_vol, 537
off_queued, 539	set_recording, 539
on_queued, 539 operator=, 534	set_snap_tick, 539
partial_assign, 534	set song mute, 537
paste selected, 550	set thru, 539
paste_trigger, 545	set_trigger_offset, 563
pause, 558	set_trigger_paste_tick, 534
perform, 564	show_events, 561
play, 541	split_trigger, 542
play_note_off, 558	stream_event, 554
play_note_on, 558	stretch_selected, 557
pop_redo, 535	toggle_playing, 538
pop_trigger_redo, 536	toggle_queued, 538
pop_trigger_undo, 536	toggle_song_mute, 537
pop_undo, 535	transpose_notes, 561
print, 541	triggerlist, 534
print_triggers, 541	triggers, 564
push_quantize, 561	unpaint_all, 557
push_trigger_undo, 535	unselect, 557
push_undo, 535	unselect_triggers, 544
put_event_on_bus, 562	us_per_quarter_note, 537
quantize_events, 560	verify_and_link, 558
remove, 563	zero_markers, 558
remove_all, 564	seq64::trigger, 568
remove_marked, 557	decrement_offset, 570
remove_selected, 557	decrement_tick_end, 570
reset, 559	decrement_tick_start, 570
reset_draw_marker, 559	increment_offset, 570
reset_draw_trigger_marker, 559	increment_tick_end, 570
select_action_e, 533	increment_tick_start, 570
select_all, 549	length, 570
select_all_notes, 549 select_events, 548	m_offset, 570
	m_selected, 570 m_tick_end, 570
select_note_events, 547 select_trigger, 543	m_tick_start, 570
selected_trigger_end, 546	offset, 570
selected_trigger_end, 546 selected_trigger_start, 546	operator<, 569
sequence, 533	selected, 570
set_32nds_per_quarter, 537	tick_end, 570
set_beat_width, 536	tick_start, 570

trigger, 569	triggers, 573
seq64::triggers, 570	unselect, 577
∼triggers, 573	seq64::user_instrument, 582
add, 575	controller_active, 584
adjust_offset, 580	controller_count, 584
adjust_offsets_to_length, 575	controller_max, 584
clear, 580	controller_name, 584
copy, 579	copy_definitions, 585
copy_selected, 577	is_valid, 583
FruityPerfInput, 581	m_controller_count, 585
GROW_END, 573	m_instrument_def, 585
GROW_MOVE, 573	m_is_valid, 585
GROW_START, 573	name, 583
get_maximum, 578	operator=, 583
get_selected_end, 578	set_controller, 584
get_selected_start, 578	set_defaults, 583
get_state, 576	set_name, 584
get_trigger_paste_tick, 580	user_instrument, 583
grow, 576	seq64::user_instrument_t, 585
grow_edit_t, 573	controllers, 585
intersect, 577	controllers_active, 586
List, 573	instrument, 585
m_clipboard, 581	seq64::user_midi_bus, 586
m_iterator_draw_trigger, 581	channel_count, 588
m_iterator_play_trigger, 581	channel_max, 588 copy_definitions, 588
m_length, 582	instrument, 588
m_parent, 581	is_valid, 587
m_paste_tick, 581 m_ppqn, 581	m_channel_count, 589
m_redo_stack, 581	m_is_valid, 588
m_trigger_copied, 581	m_midi_bus_def, 589
m triggers, 581	name, 587
m_undo_stack, 581	operator=, 587
midi_container, 581	set_defaults, 587
midifile, 581	set_instrument, 588
move, 578	set_name, 588
move_selected, 577	user_midi_bus, 587
next, 580	seq64::user midi bus t, 589
next_trigger, 580	alias, 589
operator=, 574	instrument, 589
paste, 577	seq64::user settings, 589
play, 574	add_bus, 598
pop_redo, 574	add instrument, 598
pop undo, 574	allow_two_perfedits, 600, 602
print, 574	baseline_ppqn, 602
push undo, 574	bus, 598
remove, 576	bus count, 598
remove_selected, 577	bus_instrument, 598
reset_draw_trigger_marker, 580	bus_name, 598
select, 576	BussConstIterator, 597
Seq24PerfInput, 581	BussIterator, 597
sequence, 581	Busses, 597
set_length, 574	control_height, 599, 601
set_ppqn, 574	controller_active, 598
set_trigger_paste_tick, 580	controller_name, 598
split, 576, 581	dump_summary, 601
Stack, 573	global_seq_feature, 599, 600
triggerlist, 574	gmute_tracks, 599

grid_brackets, 599, 600	m_use_new_font, 605
grid_is_black, 599	m_v_perf_page_increment, 606
grid_is_normal, 599	m_window_redraw_rate_ms, 606
grid_is_white, 599	mainwid_border, 599, 601
grid_style, 598, 600	mainwid_grid_style_t, 597
grid_style_black, 597	mainwid_spacing, 599, 601
grid_style_max, 597	mainwid_x, 599
grid_style_normal, 597	mainwid_y, 599
grid_style_white, 597	mainwnd_cols, 599, 600
instrument, 598	mainwnd_rows, 599, 600
instrument_controller_active, 598	max_sequence, 599
instrument_controller_name, 598	max_sets, 599, 601
instrument_count, 598	max_zoom, 602
instrument name, 598	mc_baseline_ppqn, 609
InstrumentConstIterator, 597	mc_max_zoom, 609
InstrumentIterator, 597	mc_min_zoom, 609
Instruments, 597	midi_beat_width, 602, 603
inverse colors, 600, 602	midi_beats_per_bar, 602, 603
m_allow_two_perfedits, 606	midi_beats_per_minute, 602, 603
m_control_height, 605	midi_buss_override, 602
m current zoom, 605	midi_ppqn, 602
m_global_seq_feature_save, 605	min zoom, 602
m_gmute_tracks, 608	normalize, 597
m_grid_brackets, 604	operator=, 597
m_grid_style, 603	perf_h_page_increment, 600, 602
m_h_perf_page_increment, 606	perf_v_page_increment, 600, 602
m_instruments, 603	private_bus, 603
m_inverse_colors, 606 m_mainwid_border, 604	private_instrument, 603 progress_bar_colored, 600, 602
m_mainwid_spacing, 604	
m mainwid_spacing, 604	progress_bar_thick, 600, 602 save_user_config, 600
m_mainwid_y, 609	
m_mainwnd_cols, 604	seqarea_seq_x, 599, 601
m mainwnd rows, 604	seqarea_seq_y, 599, 601 seqarea_x, 599, 601
m max sequence, 608	seqarea_x, 599, 601
m_max_sets, 604	sequiea_y, 555, 601 seqchars_x, 599, 601
m_midi_beat_width, 607	seqchars_x, 599, 601
m_midi_beats_per_measure, 607	seqedit_bgsequence, 600
m midi beats per minute, 607	seqedit key, 600
m midi buses, 603	seqedit_scale, 600
m_midi_buss_override, 608	seqs_in_set, 599
m_midi_ppqn, 607	set_bus_instrument, 598
m progress bar colored, 606	set defaults, 597
	-
m_progress_bar_thick, 606	set_instrument_controllers, 598
m_save_user_config, 609	text_x, 599, 601
m_seqarea_seq_x, 608	text_y, 599, 601
m_seqarea_seq_y, 608	use_new_font, 600, 602
m_seqarea_x, 608	user_settings, 597
m_seqarea_y, 608	userfile, 603
m_seqchars_x, 607	window_redraw_rate, 600, 602
m_seqchars_y, 607	zoom, 599
m_seqedit_bgsequence, 605	seq64::userfile, 610
m_seqedit_key, 605	~userfile, 611
m_seqedit_scale, 605	dump_setting_summary, 611
m_seqs_in_set, 608	parse, 611
m_text_x, 606	userfile, 611
m_text_y, 607	write, 611
m_total_seqs, 608	seq_clear_perf

seq64::seqmenu, 496	seq64::seqkeys, 485
seq_copy	seqmenu
seq64::seqmenu, 495	seq64::seqedit, 467
seq_cut	seq64::seqmenu, 493
seq64::seqmenu, 496	seqroll
seq_edit	seq64::seqdata, 452
seq64::seqmenu, 494	seq64::seqkeys, 490
seq_event_edit	seq64::seqroll, 503
seq64::seqmenu, 495	seqs_in_set
seq_event_type_t	seq64::user_settings, 599
seq64, 52	seqspec_string
seq_from_xy	seq64::editable_event, 103
seq64::mainwid, 255	seqtime
seq_in_playing_screen	seq64::seqtime, 521
seq64::perform, 393	sequence
seq_modifier_t	seq64::event_list, 135
seq64, 51	seq64::sequence, 533
seq_new	seq64::triggers, 581
seq64::seqmenu, 495	sequence_count
seq_number_size	seq64::perform, 367
seq64::midifile, 327	sequence_key
seq_paste	seq64::mainwnd, 267
seq64::seqmenu, 496	seq64::perform, 390
seq_scroll_direction_t	sequence_label
seq64, 53	seq64::perform, 390
seq_set_and_edit	sequence_max
seq64::mainwid, 253	seq64::perform, 367
seq64::seqmenu, 495	sequence_playing_change
seq_set_and_eventedit	seq64::perform, 384
seq64::mainwid, 253	sequence_playing_off
seq64::seqmenu, 495	seq64::perform, 384
seqarea_seq_x	sequence_playing_on
seq64::user_settings, 599, 601	seq64::perform, 384
seqarea_seq_y	sequence_playing_toggle
seq64::user_settings, 599, 601	seq64::perform, 383
seqarea_x	session_event
seq64::user_settings, 599, 601	seq64::jack_assistant, 203
seqarea_y	set
seq64::user_settings, 599, 601	seq64::keybindentry, 216
seqchars_x	seq64::midi_control, 291
seq64::user_settings, 599, 601	set_32nds_per_quarter
seqchars_y	seq64::perform, 369
seq64::user_settings, 599, 601	seq64::sequence, 537
seqdata	set_active
seq64::seqdata, 447	seq64::perform, 379
seqedit	set_adding
seq64::seqedit, 460	seq64::Seq24PerfInput, 441
seq64::seqroll, 517	seq64::Seq24SeqEventInput, 443
seqedit_bgsequence	seq64::seqroll, 510
seq64::user_settings, 600	set_all_key_events
seqedit_key	seq64::keys_perform, 228
seq64::user_settings, 600	seq64::keys_perform_gtk2, 234
seqedit_scale	seq64::perform, 397
seq64::user_settings, 600	set_all_key_groups
seqevent	seq64::keys_perform, 228
seq64::seqdata, 452	seq64::keys_perform_gtk2, 234
seq64::seqevent, 475	seq64::perform, 397
seqkeys	set_alsa_client_id

seq64::lash, 240	set_dirty
set_and_copy_mute_group	seq64::eventedit, 142
seq64::perform, 378	seq64::sequence, 540
set_background_sequence	set_dirty_mp
seq64::seqedit, 463	seq64::sequence, 540
seq64::seqroll, 505	set_edit_sequence
set_beat_width	seq64::perform, 368
seq64::jack_assistant, 202	seq64::seqmenu, 494
seq64::perfedit, 343	set_editing
seq64::perform, 368	seq64::sequence, 537
seq64::seqedit, 461	set_event_category
seq64::sequence, 536	seq64::eventedit, 141
set_beats_per_bar	set_event_data_0
seq64::perfedit, 343	seq64::eventedit, 141
seq64::perform, 368	set_event_data_1
seq64::seqedit, 461	seq64::eventedit, 141
seq64::sequence, 536	set_event_name
set_beats_per_measure	seq64::eventedit, 141
seq64::jack_assistant, 202	set_event_timestamp
set_beats_per_minute	seq64::eventedit, 141
seq64::jack_assistant, 202	set_group_mute_state
seq64::mastermidibus, 276	seq64::perform, 385
seq64::perform, 382	set_guides
set_bus_and_midi_channel	seq64::perfedit, 343
seq64::seqmenu, 496	seq64::perfroll, 411
set_bus_instrument	seq64::perftime, 423
seq64::user_settings, 598	set_have_redo
set_channel	seq64::perform, 374
seq64::event, 121	seq64::sequence, 535
set_clock	set_have_undo
seq64::mastermidibus, 280	seq64::perform, 374
seq64::midibus, 311	seq64::sequence, 535
set_clock_mod	set_hint_key
seq64::midibus, 311 set_config_files	seq64::seqkeys, 486
seq64::rc_settings, 435	set_hint_state seq64::seqkeys, 486
seq04rc_settings, 433 set_controller	set_hold_undo
seq64::user_instrument, 584	set_noid_undo seq64::sequence, 535
set_current_drop_x	set_image
seq64::gui_drawingarea_gtk2, 186	set_image seq64::mainwnd, 265
set_current_drop_y	seq64::marriwrid, 200
seq64::gui_drawingarea_gtk2, 186	set_input
set_current_event	seq64::mastermidibus, 281
seq64::eventslots, 151	seq64::midibus, 311
set current offset x y	set_input_bus
seq64::seqroll, 513	seq64::perform, 391
set_data	set instrument
seq64::event, 122	set_mstrument seq64::user_midi_bus, 588
set_data_type	set_instrument_controllers
seq64::seqdata, 448	seq64::user_settings, 598
seq64::sequala, 446 seq64::seqedit, 464	set_jack_running
seq64::seqevent, 476	seq64::jack_assistant, 206
seq64::seqroll, 505	set_jack_tick
set defaults	set_jack_tick seq64::perform, 372
seq64::rc_settings, 432	set_key
seq64::user_instrument, 583	seq64::seqedit, 463
seq64::user_midi_bus, 587	seq64::seqkeys, 486
seq04::user_settings, 597	seq64::seqrell, 504

set_key_event	seq64::sequence, 562
seq64::keys_perform, 228	set_playback_mode
seq64::perform, 397	seq64::perform, 394
set_key_group	set_playing
seq64::keys_perform, 228	seq64::sequence, 538
seq64::perform, 398	set_playing_screenset
set_keys	seq64::keys_perform, 224
seq64::keys_perform, 222	seq64::perform, 376
set_last_tick	set_position
	
seq64::sequence, 538	seq64::jack_assistant, 209
set_left_tick	set_ppqn
seq64::perform, 372	seq64::jack_assistant, 205
set_length	seq64::mastermidibus, 276
seq64::sequence, 537	seq64::perfroll, 412
seq64::triggers, 574	seq64::perftime, 424
set_line	seq64::triggers, 574
seq64::gui_drawingarea_gtk2, 180	set_quantized_rec
set_listen_button_press	seq64::sequence, 539
seq64::seqkeys, 486	set raise
set_listen_button_release	seq64::sequence, 537
seq64::seqkeys, 486	set_rec_vol
set_listen_motion_notify	seq64::seqedit, 461
seq64::seqkeys, 487	seq64::sequence, 537
set_looped	set_recording
seq64::perfedit, 344	seq64::sequence, 539
set_looping	set_right_tick
seq64::perform, 383	seq64::perform, 373
set_master_midi_bus	set_running
seq64::sequence, 547	seq64::perform, 394
set_measures	set_scale
seq64::seqedit, 462	seq64::perftime, 423
seq64::sequence, 536	seq64::seqedit, 463
set_midi_bus	seq64::seqkeys, 486
seq64::seqedit, 463	seq64::seqroll, 505
seq64::sequence, 547	set_screen_set_notepad
set_midi_channel	seq64::perform, 376
seq64::seqedit, 463	• •
·	set_screenset seq64::mainwid, 252
seq64::sequence, 541	•
set_mode_group_learn	seq64::perform, 376
seq64::perform, 378	set_seq_count
set_mode_group_mute	seq64::eventedit, 141
seq64::perform, 377	set_seq_ppqn
set_name	seq64::eventedit, 141
seq64::sequence, 536	set_seq_time_sig
seq64::user_instrument, 584	seq64::eventedit, 141
seq64::user_midi_bus, 588	set_seq_title
set note	seq64::eventedit, 140
seq64::event, 124	set_sequence_control_status
set_note_length	seq64::perform, 383
-	• •
seq64::seqedit, 461	set_sequence_input
seq64::seqroll, 504	seq64::mastermidibus, 279
set_note_velocity	set_snap
seq64::event, 124	seq64::perfedit, 343
set_offset	seq64::seqedit, 461
seq64::perform, 386	seq64::seqevent, 476
set_orig_ticks	seq64::seqroll, 504
seq64::perform, 382	set_snap_tick
set_parent	seq64::sequence, 539
	· · · · ·

set_song_mute	signal_action
seq64::mainwnd, 267	seq64::mainwnd, 269
seq64::perform, 377	size
seq64::sequence, 537	seq64::midi_container, 286
set_start_tick	seq64::midi_list, 294
seq64::perform, 372	seq64::midi_vector, 305
set_status	SlotMap
seq64::event, 120, 121	seq64::keys_perform, 222
set_status_from_string	sm_category_arrays
seq64::editable event, 102	seq64::editable_event, 104
set_status_keep_channel	sm_category_names
seq64::event, 121	seq64::editable_event, 104
set_sysex_size	sm_channel_event_names
seq64::event, 123	seq64::editable_event, 104
set text	sm_cond
seq64::eventslots, 154	seq64::condition_var, 92
set_thru	sm_internal_keys
seq64::sequence, 539	seq64::gui_assistant_gtk2, 176
set_timestamp	sm mc dummy
seg64::event, 118	seq64::perform, 399
set_transposable	sm meta event names
seq64::seqmenu, 496	seq64::editable event, 104
set_trigger_offset	sm_prop_event_names
seq64::sequence, 563	seq64::editable_event, 104
set_trigger_paste_tick	sm_recursive_mutex
seq64::sequence, 534	seq64::mutex, 330
seq64::triggers, 580	sm_status_pairs
set_was_active	seq64::jack_assistant, 212
seq64::perform, 380	sm_system_event_names
set zoom	seq64::editable_event, 104
seq64::perfedit, 343	snap_x
seq64::perfroll, 414	seq64::perfroll, 413
seq64::perftime, 423	seq64::seqevent, 478
seq64::seqdata, 448	seq64::seqroll, 507
seq64::seqedit, 460	snap_y
seq64::seqevent, 476	seq64::seqevent, 478
seg64::segroll, 504	seg64::segroll, 507
seq64::seqtime, 522	snapshot_1
shift lock	seq64::keys_perform, 224
seq64::keystroke, 238	snapshot_2
shorten_file_spec	seq64::keys_perform, 224
seq64, 59	song_fill_seq_event
show events	seq64::midi container, 288
seq64::sequence, 561	song_fill_seq_trigger
show midi	seq64::midi_container, 288
seq64::rc_settings, 433, 434	song_start_mode
show_position	seq64::perform, 369
seq64::jack_assistant, 208	seq64::rc_settings, 433, 434
show_statuses	split
seq64::jack_assistant, 207	seq64::midi_splitter, 299
show_ui_sequence_key	seq64::triggers, 576, 581
seq64::keys_perform, 226	split_channel
seq64::perform, 386	seq64::midi_splitter, 299
show_ui_sequence_number	split_trigger
seq64::keys_perform, 226	seq64::perform, 374
seq64::perform, 387	seq64::perfroll, 413
signal	seq64::sequence, 542
seq64::condition_var, 92	Stack

seq64::triggers, 573	sysex
start	seq64::mastermidibus, 279
seq64::jack_assistant, 203	seq64::midibus, 310
seq64::keys_perform, 225	SysexContainer
seq64::lash, 240	seq64::event, 116
seq64::mastermidibus, 277	tompo to uo
seq64::midibus, 310	tempo_to_us
seq64::perform, 378	seq64, 62
start_jack	tempo_us_from_beats_per_minute
seq64::perform, 379	seq64, 62
start_key	tempo_us_to_bytes seq64, 61
seq64::perform, 389	•
start_paste	text_x
seq64::seqevent, 477	seq64::user_settings, 599, 601
seq64::seqroll, 506	text_y seq64::user_settings, 599, 601
start_playing	thru_change_callback
seq64::mainwnd, 266	seq64::seqedit, 464
seq64::perfedit, 345	tick_end
seq64::perform, 388	seq64::trigger, 570
stats	tick_multiplier
seq64::rc_settings, 433, 434	seq64::jack_assistant, 206
status	tick offset
seq64::midi_control, 291	seq64::perftime, 424
status_string	tick start
seq64::editable_event, 103	seq64::trigger, 570
stock_event_string	tick_to_pixel
seq64::editable_event, 103	seq64::perftime, 424
stop	ticks_to_delta_time_us
seq64::jack_assistant, 203	seq64, 63
seq64::keys_perform, 226	time_as_measures
seq64::mastermidibus, 278	seq64::editable_event, 102
seq64::midibus, 310	time_as_minutes
seq64::perform, 378	seq64::editable_event, 102
stop_jack	time_as_pulses
seq64::perform, 379	seq64::editable_event, 102
stop_key	timeout
seq64::perform, 389	seq64::mainwid, 255
stop_playing	seq64::perfedit, 344
seq64::mainwnd, 266	seq64::seqedit, 466
seq64::perfedit, 345	timer_callback
seq64::perform, 389	seq64::mainwnd, 265
stream_event	timestamp
seq64::sequence, 554	seq64::editable_event, 102
stretch_selected	timestamp_format_t
seq64::sequence, 557	seq64::editable_event, 99
string_is_void	timestamp_measures
seq64, 60	seq64::editable_event, 100
string_not_void	timestamp_pulses
seq64, 59	seq64::editable_event, 100
string_to_midibyte	timestamp_string
seq64, 59	seq64::editable_event, 102
string_to_pulses	timestamp_time
seq64, 58	seq64::editable_event, 100
seq64::editable_events, 108	timestring_to_pulses
strings_match	seq64, 58
seq64, 60	timing
sync	seq64::editable_events, 108
seq64::jack_assistant, 209	to_string

seq64, 67	unpaint_all
toLower	seq64::event_list, 134
seq64::mainwnd, 267	seq64::sequence, 557
toggle_all_tracks	unselect
seq64::perform, 384	seq64::event, 124
seq64::seqmenu, 496	seq64::sequence, 557
toggle_current_sequence	seq64::triggers, 577
seq64::seqmenu, 494	unselect_all
toggle_playing	seq64::event_list, 134
seq64::mainwnd, 266	unselect_triggers
seq64::perfedit, 345	seq64::sequence, 544
seq64::sequence, 538	unset_edit_sequence
toggle_queued	seq64::perform, 368
seq64::sequence, 538	seq64::seqmenu, 494
toggle_song_mute	unset_mode_group_learn
seq64::sequence, 537	seq64::perform, 378
toggle_song_start_mode	unset_mode_group_mute
seq64::perform, 369	seq64::perform, 377
toggle_visible	unset_sequence_control_status
seq64::lfownd, 243	seq64::perform, 383
top_index	update_all_windows
seq64::eventslots, 151	seq64::seqedit, 464
track_end_size	update_and_draw
seq64::midifile, 327	seq64::seqroll, 506
track_name_size	update_background
seq64::midifile, 326	seq64::seqroll, 505
transport_callback	update_mainwid_sequences
seq64::options, 332	seq64, 75
transport_state	seq64::mainwid, 257
seq64::jack_assistant, 202	update_markers
transpose_notes	seq64::mainwid, 254
seq64::sequence, 561	update_mouse_pointer
trigger	seq64::FruityPerfInput, 166
seq64::trigger, 569	seq64::FruitySeqEventInput, 168
triggerlist	seq64::FruitySeqRollInput, 171
seq64::sequence, 534	seq64::seqroll, 511
seq64::triggers, 574 triggers	update_perfedit_sequences
seg64::sequence, 564	seq64, 75
seq64::triggers, 573	seq64::perfedit, 345
type	update_pixmap
seq64::keybindentry, 215	seq64::perftime, 425
Sequalities of the sequence of	seq64::seqdata, 448
undo	seq64::seqevent, 477
seq64::perfedit, 344	seq64::seqkeys, 487
undo_callback	seq64::seqroll, 505
seq64::seqedit, 464	seq64::seqtime, 522
unlock	update_sequences_on_window
seq64::mutex, 330	seq64::mainwid, 253
unmark	update_sizes
seq64::event, 123	seq64::perfroll, 411
unmark_all	seq64::perftime, 424
seq64::event_list, 133	seq64::seqdata, 448
unmodify	seq64::seqevent, 476
seq64::event_list, 131	seq64::seqkeys, 487
unmute_all_tracks	seq64::seqroll, 505
seq64::seqmenu, 496	seq64::seqtime, 522
unpaint	update_window_title
seq64::event, 123	seq64::mainwnd, 267
	-

	22204 05
us_per_quarter_note	seq64, 65
seq64::perform, 369	wave_type_t
seq64::sequence, 537	seq64, 51
use_new_font	white
seq64::user_settings, 600, 602	seq64::gui_palette_gtk2, 192
user_filename	white_key
seq64::rc_settings, 433, 436	seq64::gui_palette_gtk2, 193
user_filename_alt	white_paint
seq64::rc_settings, 434, 436	seq64::gui palette gtk2, 193
user_filespec	width
seq64::rc_settings, 432	seq64::gui_drawingarea_gtk2::rect, 439
user_instrument	seq64::rect, 439
	window_redraw_rate
seq64::user_instrument, 583	
user_midi_bus	seq64::user_settings, 600, 602
seq64::user_midi_bus, 587	window_x
user_settings	seq64::gui_drawingarea_gtk2, 179
seq64::user_settings, 597	window_y
userfile	seq64::gui_drawingarea_gtk2, 179
seq64::user_settings, 603	with_jack
seq64::userfile, 611	seq64::rc_settings, 433
usr	with_jack_master
seq64, 73	seq64::rc_settings, 433, 434
3340 1, 70	with_jack_master_cond
v_adjustment	seq64::rc_settings, 433, 434
seq64::eventedit, 142	
valid_sequence	with_jack_transport
	seq64::rc_settings, 433, 434
seq64::mainwid, 254	write
value_to_name	seq64::configfile, 95
seq64::editable_event, 101	seq64::midifile, 317
varinum_size	seq64::optionsfile, 336
seq64::midifile, 325	seq64::userfile, 611
verify_and_link	write_byte
seq64::event_list, 133	seq64::midifile, 322
seq64::sequence, 558	write header
versiontext	seq64::midifile, 324
seq64, 82	write_long
vertical_adjust	_ ·
	seq64::midifile, 321
seq64::perfroll, 414	write_options_files
seq64::seqedit, 462	seq64, 66
seq64::seqroll, 507	write_prop_header
vertical_set	seq64::midifile, 324
seq64::perfroll, 414	write_proprietary_track
seq64::seqedit, 462	seq64::midifile, 325
	write seg number
WAVE_INVERSE_TRIANGLE	seq64::midifile, 323
seq64, 51	write short
WAVE NONE	seq64::midifile, 321
seq64, 51	•
WAVE SINE	write_song
seq64, 51	seq64::midifile, 317
WAVE STEP	write_track
_	seq64::midifile, 327
seq64, 51	write_track_end
WAVE_TRIANGLE	seq64::midifile, 323
seq64, 51	write_track_name
WHITE	seq64::midifile, 323
seq64::font, 161	write varinum
wait	seq64::midifile, 322
seq64::condition_var, 92	30q0+mailli6, 022
wave func	X

```
seq64::click, 90
    seq64::gui_drawingarea_gtk2::rect, 439
    seq64::rect, 439
x_to_w
    seq64::seqevent, 477
xy_to_rect
    seq64::seqdata, 449
    seq64::seqroll, 508
у
    seq64::click, 90
    seq64::gui_drawingarea_gtk2::rect, 439
    seq64::rect, 439
YELLOW_ON_BLACK
    seq64::font, 161
yellow
    seq64::gui_palette_gtk2, 193
zero_markers
    seq64::sequence, 558
zoom
    seq64::user_settings, 599
zoom_check
    seq64::perfedit, 342
zoom_power_of_2
    seq64, 61
```