Sequencer64 Developer Reference Manual

0.9.16

Generated by Doxygen 1.8.11

Contents

Chapter 1

Sequencer64

Author(s) Chris Ahlstrom 2015-11-27

1.1 Introduction

Sequencer64 is a major cleanup, refactoring, and documentation of the Seq24 live-play MIDI sequencer.

The current document, generated by Doxygen, describes the functions, classes, modules, and other entities used in this project.

Also read the ROADMAP, README, and contrib/bugs_to_investigate files to understand the genesis of this project and the things that still need to be done with Sequencer64.

Also, we have pretty deeply documented *Seq24* and *Sequencer64* with PDF files that can be generated by git-cloning the following projects, installing a number of tools related to PDF and LaTeX, and running "make":

- https://github.com/ahlstromcj/seq24-doc.git
- https://github.com/ahlstromcj/sequencer64-doc.git

These project also have prebuilt PDFs should one not want to bother building them.

In the present document, we've left out a fair amount of side-code to cut down on the size of the document. For example, the main module, redundant Windows support, utility headers like easy_macros.h, standard stuff like the mutex module, the fruity variants (at least the ones already refactored into their own modules), etc., are all left out. Still, the resulting PDF is over 300 pages long.

Some useful references:

- http://acad.carleton.edu/courses/musc108-00-f14/pages/04/04StandardMIDIFiles.html
- http://www.midimusicadventures.com/qs/midi-zips/soundtracks/kq6gm.zip

Chapter 2

MIDI File Parsing in Sequencer64

Author(s) Chris Ahlstrom 2016-02-13

2.1 Introduction

This section describes the parsing of a MIDI file (and a few other topics). We wanted to add the reading of SMF 0 files to *Sequencer64*. We started with the main format that is supported, SMF 1. Once we understood that we, we figured out how to split a SMF 0 tracks correctly.

We split the midifile::parse() function into two sections. The first section analyzes the header of the MIDI. Then, based on whether the file is SMF 1 (the normal case) or SMF 0, either the parse_smf_1() function of or the parse_smf_0() function is called. The parse_smf_0() function creates one sequence object per channel present in the SMF 0 file, plus the original track. The last pattern slot (sequence 16) will contain the original track data, and the rest will contain common data and then channel data for each channel. After the parsing is done, all the tracks (including the original track) will be added to the performance. The user then has the option of deleting the original track, which will be the last track.

2.2 SMF 1 Parsing

This section describes the parsing of the header chunk, MThd, and the track chunk, MTrk.

The midifile::parse() function starts by opening the MIDI file, getting its file-size, pre-allocating the data vector to that size, reading all of the characters into that vector, and then closing the file.

2.2.1 MIDI File Header, MThd

The data of the header is read:

```
Header ID:     "MThd"         read_long()       4 bytes
MThd length:     6            read_long()       4 bytes
Format:        0, 1, 2        read_short()      2 bytes
No. of track:  1 or more      read_short()      2 bytes
PPQN:           192           read_short()      2 bytes
```

The header ID and it's length are always the same values. The formats that Sequencer64 supports are 0 or 1. SMF 0 has only one track, while SMF 1 can support an arbitary number of tracks. The last value in the header is the PPQN value, which specifies the "pulses per quarter note", which is the basic time-resolution of events in the MIDI file. Common values are 96 or 192, but higher values are also common. Sequencer64 and its precursor, Seq24, default to 192.

2.2.2 MIDI Track, MTrk

Sequencer64 next reads the tracks specified in the file. Each track is assumed to cover a different MIDI channel, but always the same MIDI buss. (The MIDI buss is not a data item in standard MIDI files, but it is a special data item in Seq24/Sequencer64 MIDI files.) Each track is tagged by a standard chunk marker, "MTrk". Other markers are possible, and are to be ignored, if nothing else. Here are the values read at the beginning of a track:

```
Track ID:      "MTrk"         read_long()       4 bytes
Track length:  varies         read_long()       4 bytes
```

The track length is the number of bytes that need to be read in order to get all of the data in the track.

Next, a new sequence object is created, with the PPQN value passed to its constructor. The sequence then is hooked to the master MIDI buss object. The "RunningTime" accumulator is set to 0 for that track.

Next, the parse() function loops through the rest of the track, reading data and logging it to the sequence. Let's go through the loop, which is the meat of the processing.

TODO: An empty event is created before track processing, and re-used for every track and event. This seems dangerous. We moved the event constructor two levels of nesting deeper, and it seems to work fine.

Delta time. The amount time that passes from one event to the next is the *delta time*. For some events, the time doesn't matter, and is set to 0. This values is a *variable length value*, also known as a "VLV" or a "varinum". It provides a way of encoding arbitrarily large values, a byte at a time. For now, just note that a varinum is 1 or more bytes, and MIDI provides a way to tell when the varinum is complete.

```
Delta time:    varies         read_varinum()    1 or more bytes
```

2.2.2.1 Channel Events

Status. The byte after the delta time is examined by masking it against 0x80 to check the high bit. If not set, it is a "running status", it is replaced with the "last status", which is 0 at first.

```
Status byte:   varies         read_byte()       1 byte
```

If the high bit is set, it is a status, and is passed to the setter `event::set_status()`.

The "RunningTime" accumulator is incremented by the delta-time. The current time is adjusted as per the PPQN ratio, if needed, and passed to the setter `event::set_timestamp()`.

Now what does the status mean? First, the channel part of the status is masked out using the 0xF0 mask.

If it is a 2-data-byte event (note on, note off, aftertouch, control-change, or pitch-wheel), then the two data bytes are read:

```
Data byte 0:   varies         read_byte()       1 byte
Data byte 1:   varies         read_byte()       1 byte
```

If the status is a note-on event, with data[1] = 0, then it is converted to a note-off event, a fix for the output quirks of some MIDI devices, and the status of the event is amended to EVENT_NOTE_OFF.

If it is a 1-data-btye event (program change or channel pressure), then only data byte 0 is read.

Then the one or two data bytes are added to the event by overloads of `event::set_data()`, the event is added to the current sequence by `sequence::add_event()`, and the MIDI channel of the sequence is set by `sequence::set_midi_channel()`.

Note that this is the point where parsing could detect a change in channel, and select a new sequence to support that channel, and add the events to that sequence, if the file were SMF 0.

Also note that the channel of the sequence is set every a new channel event/status is read. This should be done once, and then simply warned about if a non-matching channel occurs.

Lastly, note that it might be better to do the sequence function calls at the end of processing the event.

2.2.2.2 Meta Events

If the event status masks off to 0xF0 (0xF0 to 0xFF), then it is a meta event. If the status is 0xFF, it is called a "Sequencer-specific", or "SeqSpec" event. For this kind of event, then a type byte and the length of the event are read.

```
Meta type:     varies         read_byte()       1 byte
Meta length:   varies         read_varinum()    1 or more bytes
```

If the type of the SeqSpec (0xFF) meta event is 0x7F, parsing checks to see if it is one of the Seq24 "proprietary" events. These events are tagged with various values that mask off to 0x24240000. The parser reads the tag:

```
Prop tag:     0x242400nn      read_long()       4 bytes
```

These tags provide a way to save and recover Seq24/Sequencer64 properties from the MIDI file: MIDI buss, MIDI channel, time signature, sequence triggers, and (new), the key, scale, and background sequence to use with the track/sequence. Any leftover data for the tagged event is let go. Unknown tags ate skipped.

If the type of the SeqSpec (0xFF) meta event is 0x2F, then it is the End-of-Track marker. The current time is set using `sequence::set_length()` and then `sequence::zero_markers()` is called, and parsing is done for that track.

If the type of the SeqSpec (0xFF) meta event is 0x03, then it is the sequence name. The "length" number of bytes are read, and loaded by `sequence::set_name()`.

If the type of the SeqSpec (0xFF) meta event is 0x00, then it is the sequence number, which is read:

```
Seq number:    varies         read_short()      2 bytes
```

Note that the sequence number might be modified latter to account for the current screenset in force for a file import operation.

Anything other SeqSpec type is simply skipped by reading the "length" number of bytes.

To summarize the process, here are the relevant event and sequence setter calls typically made while parsing a MIDI track:

1. `perform::add_sequence()`
   (a) `sequence::sequence()`
   (b) `sequence::set_master_midi_bus())`
   (c) `sequence::add_event()`
      i. `event::event()`
      ii. `event::set_status()`
      iii. `event::set_timestamp()`
      iv. `event::set_data()`
   (d) `sequence::set_midi_channel()`
   (e) `sequence::set_length()`
   (f) `sequence::zero_markers()`
   (g) `sequence::set_name()`
   (h) `sequence::set_midi_bus()`
2. `xxxxx::yyyy()`

2.2.3 Meta Events Summary

Here, we summarize the MIDI meta events for your edification.

1. `FF 00 02 ssss`: Sequence Number.
2. `FF 01 len text`: Text Event.
3. `FF 02 len text`: Copyright Notice.
4. `FF 03 len text`: Sequence/Track Name.
5. `FF 04 len text`: Instrument Name.
6. `FF 05 len text`: Lyric.
7. `FF 06 len text`: Marker.
8. `FF 07 len text`: Cue Point.
9. `FF 08 len text`: Patch/program Name.
10. `FF 09 len text`: Device Name.
11. `FF 0A through 0F len text`: Other kinds of text events.
12. `FF 20 01 cc`: MIDI channel (obsolete, used by Cakewalk)
13. `FF 21 01 pp`: MIDI port (obsolete, used by Cakewalk)
14. `FF 2F 00`: End of Track.
15. `FF 51 03 tttttt`: Set Tempo, us/qn.
16. `FF 54 05 hr mn se fr ff`: SMPTE Offset.
17. `FF 58 04 nn dd cc bb`: Time Signature.
18. `FF 59 02 sf mi`: Key Signature.
19. `FF 7F len data`: Sequencer-Specific.

The next sections describe the events that *Sequencer* tries to handle. These are

- Sequence Number (0x00)
- Track Name (0x03)
- End-of-Track (0x2F)
- Set Tempo (0x51) (Sequencer64 only)
- Time Signature (0x58) (Sequencer64 only)
- Sequencer-Specific (0x7F)
- System Exclusive (0xF0) Sort of handled, functionality incomplete..

2.2.3.1 Sequence Number (0x00)

```
FF 00 02 ss ss
```

This optional event must occur at the beginning of a track, before any non-zero delta-times, and before any transmittable MIDI events. It specifies the number of a sequence.

2.2.3.2 Track/Sequence Name (0x03)

```
FF 03 len text
```

If in a format 0 track, or the first track in a format 1 file, the name of the sequence. Otherwise, the name of the track.

2.2.3.3 End of Track (0x2F)

```
FF 2F 00
```

This event is not optional. It is included so that an exact ending point may be specified for the track, so that it has an exact length, which is necessary for tracks which are looped or concatenated.

2.2.3.4 Set Tempo Event (0x51)

The MIDI Set Tempo meta event sets the tempo of a MIDI sequence in terms of the microseconds per quarter note. This is a meta message, so this event is never sent over MIDI ports to a MIDI device.

After the delta time, this event consists of six bytes of data:

```
FF 51 03 tt tt tt
```

Example:

```
FF 51 03 07 A1 20
```

1. 0xFF is the status byte that indicates this is a Meta event.
2. 0x51 the meta event type that signifies this is a Set Tempo event.
3. 0x03 is the length of the event, always 3 bytes.
4. The remaining three bytes carry the number of microseconds per quarter note. For example, the three bytes above form the hexadecimal value 0x07A120 (500000 decimal), which means that there are 500,000 microseconds per quarter note.

Since there are 60,000,000 microseconds per minute, the event above translates to: set the tempo to 60,000,000 / 500,000 = 120 quarter notes per minute (120 beats per minute). This is a 24-bit binary value, so each byte covers the full range of 0x00 to 0xFF.

This event normally appears in the first track. If not, the default tempo is 120 beats per minute. This event is important if the MIDI time division is specified in "pulses per quarter note", which does not itself define the length of the quarter note. The length of the quarter note is then determined by the Set Tempo meta event.

Representing tempos as time per beat instead of beat per time allows absolutely exact DWORD-term synchronization with a time-based sync protocol such as SMPTE time code or MIDI time code. This amount of accuracy provided by this tempo resolution allows a four-minute piece at 120 beats per minute to be accurate within 500 usec at the end of the piece.

We have now added the Tempo meta event (and the Time Signature meta event) to the track, which allows other sequencers to obtain these values from a Sequencer64 MIDI file. Here are the original headers for a normal MIDI file and its legacy (Seq24) conversion, as shown by the midicvt application:

```
hymne.asc

MThd 1 4 96
MTrk
0 Meta SeqName "Vangelis: Hymne"
0 TimeSig 4/4 24 8
0 Tempo 750000
0 Meta TrkEnd
TrkEnd
```

```
hymne-ppqn-384.asc

MThd 1 4 384
MTrk
0 SeqNr 0
0 Meta SeqName "Vangelis: Hymne"
0 SeqSpec 24 24 00 08       (no triggers)
0 SeqSpec 24 24 00 01 00    (MIDI buss 0)
0 SeqSpec 24 24 00 06 04 04 (beats, width)
0 SeqSpec 24 24 00 02 00    (MIDI ch. 0)
96 Meta TrkEnd
TrkEnd
```

Here is the header data that result from the new conversion, which is used if the "legacy" option is not in force:

```
MThd 1 4 192
MTrk
0 SeqNr 0
0 Meta SeqName "Vangelis: Hymne"
0 TimeSig 4/4 24 8
0 Tempo 750000
0 SeqSpec 24 24 00 08
0 SeqSpec 24 24 00 01 00
0 SeqSpec 24 24 00 06 04 04
0 SeqSpec 24 24 00 02 00
48 Meta TrkEnd
TrkEnd
```

2.2.3.5 Time Signature Event (0x58)

After the delta time, this event consists of seven bytes of data:

```
FF 58 04 nn dd cc bb
```

The time signature is expressed as four numbers. `nn` and `dd` represent the numerator and denominator of the time signature as it would be notated. The numerator counts the number of beats in a measure (beats per measure or beats per bar). The denominator is a negative power of two: 2 represents a quarter-note, 3 represents an eighth-note, etc. The denominator specifies the unit of the beat (e.g. 4 or 8). In Seq24/Sequencer64, this value is also called the "beat width".

The `cc` parameter expresses the number of MIDI clocks (or "ticks", or "pulses") in a metronome click. The standard MIDI clock ticks 24 times per quarter note, so a value of 6 would mean the metronome clicks every 1/8th note. A `cc` value of 6 would mean that the metronome clicks once every 1/8th of a note (quaver). This MIDI clock is different from the clock (PPQN) that determines the start time and duration of the notes.

The `bb` parameter expresses the number of notated 32nd-notes in a MIDI quarter note (24 MIDI Clocks). The usual value for this parameter is 8, though some sequencers allow the user to specify that what MIDI thinks of as a quarter note, should be notated as something else. For example, a value of 16 means that the music plays two quarter notes for each quarter note metered out by the MIDI clock, so that the music plays at double speed.

Examples:

```
FF 58 04 04 02 18 08
```

1. 0xFF is the status byte that indicates this is a Meta event.
2. 0x58 the meta event type that signifies this is a Time Signature event.

3. 0x04 is the length of the event, always 4 bytes.

4. 0x04 is the numerator of the time signature, and ranges from 0x00 to 0xFF.

5. 0x02 is the log base 2 of the denominator, and is the power to which 2 must be raised to get the denominator. Here, the denominator is 2 to 0x02, or 4, so the time signature is 4/4.

6. 0x18 is the metronome pulse in terms of the number of MIDI clock ticks per click. Assuming 24 MIDI clocks per quarter note, the value here (0x18 = 24) indidicates that the metronome will tick every 24/24 quarter note. If the value of the sixth byte were 0x30 = 48, the metronome clicks every two quarter notes, i.e. every half-note.

7. 0x08 defines the number of 32nd notes per beat. This byte is usually 8 as there is usually one quarter note per beat, and one quarter note contains eight 32nd notes.

A time signature of 6/8, with a metronome click every 3rd 1/8 note, would be encoded:

```
FF 58 04 06 03 24 08
```

Remember, a 1/4 note is 24 MIDI Clocks, therefore a bar of 6/8 is 72 MIDI Clocks. Hence 3 1/8 notes is 36 (=0x24) MIDI Clocks.

There should generally be a Time Signature Meta event at the beginning of a track (at time = 0), otherwise a default 4/4 time signature will be assumed. Thereafter they can be used to effect an immediate time signature change at any point within a track.

For a format 1 MIDI file, Time Signature Meta events should only occur within the first MTrk chunk.

If a time signature event is not present in a MIDI sequence, 4/4 signature is assumed.

In *Sequencer64*, the c_timesig SeqSpec event is given priority. The conventional time signature is used only if the c_timesig SeqSpec is not present in the file. NEEDS TO BE TESTED.

2.2.3.6 SysEx Event (0xF0)

If the meta event status value is 0xF0, it is called a "System-exclusive", or "SysEx" event.

```
F0 len data F7
```

Sequencer64 has some code in place to store these messages, but the data is currently not actually stored or used. Although there is some infrastructure to support storing the SysEx event within a sequence, the SysEx information is simply skipped. *Sequencer64* warns if the terminating 0xF7 SysEx terminator is not found at the expected length. Also, some malformed SysEx events have been encountered, and those are detected and skipped as well.

2.2.3.7 Sequencer Specific (0x7F)

This data, also known as SeqSpec data, provides a way to encode information that a specific sequencer application needs, while marking it so that other sequences can safely ignore the information.

```
FF 7F len data
```

In *Seq24* and *Sequencer64*, the data portion starts with four bytes that indicate the kind of data for a particular SeqSpec event:

```
c_midibus        ^  0x24240001  Track buss number
c_midich         ^  0x24240002  Track channel number
c_midiclocks     *  0x24240003  Track clocking
c_triggers       ^  0x24240004  See c_triggers_new
c_notes          *  0x24240005  Song data, notes
c_timesig        ^  0x24240006  Track time signature
c_bpmtag         *  0x24240007  Song beats/minute
c_triggers_new   ^  0x24240008  Track trigger data
c_mutegroups     *  0x24240009  Song mute group data
c_midictrl       *  0x24240010  Song MIDI control
c_musickey       +  0x24240011  Track key (Sequencer64 only)
c_musicscale     +  0x24240012  Track scale (Sequencer64 only)
c_backsequence   +  0x24240013  Track background sequence (Sequencer64 only)

* = global only; ^ = track only; + = both
```

In *Seq24*, these events are placed at the end of the song, but are not marked as SeqSpec data. Most MIDI applications handle this situation fine, but some (e.g. midicvt) do not. Therefore, *Sequencer64* makes sure to wrap each data item in the 0xFF 0x7F wrapper.

Also, the last three items above (key, scale, and background sequence) can also be stored (by *Sequencer64*) with a particular sequence/track, as well as at the end of the song. Not sure if this bit of extra flexibility is useful, but it is there.

2.2.3.8 Non-Specific End of Sequence

Any other statuses are deemed unsupportable in *Sequencer64*, and abort parsing with an error.

If the –bus option is in force, `sequence::set_midi_bus()` is called to override the buss number (if any) stored with the sequence.

Finally, `perform::add_sequence()` adds the sequence to the encoded tune.

2.3 SMF 0 Parsing

After parsing SMF 1 track data, we end up with a number of sequences, each on a different MIDI channel. With SMF 0, data for all channels is present in a single track. Sequencer64 will read SMF 0 data, but we really need to be able to have one MIDI channel per track. So we need to take the data from the sequence and use it to make more sequences.

- `sequence::add_event()`.
- `sequence::set_midi_channel()`.
- `sequence::set_length()`.
- `sequence::set_midi_bus()`.
- `perform::add_sequence()`.

This code basically works. For now, please look at the source code for more details. Also, the reading of SMF 0 MIDI files is described in the *sequencer64-doc* project on GitHub.

2.4 Running Status

When we apply the `midicvt` application to a file saved by *Sequencer64*, we can end up with a successful ASCII conversion that ends with an error message:

```
$ midicvt hymne-seq64.midi -o hymne-seq64.asc
? Error at MIDI file offset 12155 [0x2f7b]
Error: Garbage at end 'readtrack(): unexpected running status'
```

Is this a problem in `midicvt` or *Sequencer4*? Let's learn about running status.

Running status is a way to speed up the sending of MIDI bytes to a synthesizer or sequencer by taking advantage of redundancy where possible. For example, if we're sending a consecutive group of Note On and Note Off messages to a particular channel, we can save some time by not sending the channel status byte after the first time. Here's an example with Note On on channel 1:

```
0x90 3C 7F
0x90 40 7F
0x90 43 F3
```

Since no change in status occurs after the first of these three events, we can drop the subsequent status bytes:

```
0x90 3C 7F
40 7F
43 F3
```

The 0x90 byte is saved in a "running status buffer" (RSB), and is filled in by the receiving device.

Here is the sequence of events for operating with running status.

1. Clear the RSB buffer (RSB = 0) to start.
2. If a **Voice Category Status** (VCS) byte is received, then set RSB = VCS. VCS bytes range from 0x80 to 0xEF. This is binary 1000000 to 11100000.
3. If a data byte is received (data bytes range from 0x00 to 0x7F, binary 0000000 to 0111111; that is, bit 7 is always 0 in a data byte):
   (a) If RSB != 0, first insert the RSB into the incoming data stream, then insert the data byte.
   (b) If RSB == 0, then just insert the data byte into the incoming data stream.
4. Clear the RSB buffer (RSB = 0) when a System Common Message (SCM) status byte is received. SCM bytes range from 0xF0 to 0xF7.
5. The message after an SCM **must** begin with a status byte. That is a byte with bit 7 set.
6. Do no special action when a Realtime Category Message (RCM) byte is received. RCM bytes range from 0xF8 to 0xFF.

Note that some events, such as Tempo, assume that its bytes are all data bytes.

Chapter 3

JACK, Live, and Song Modes in Sequencer64

Author(s) Chris Ahlstrom 2016-01-23

3.1 Introduction

This section describes the interactions between JACK settings and the Live/Song Mode settings, with an eye to describing the proper behavior of Sequencer64 with JACK settings, how the Live/Song modes are supposed to work, and what bugs or issues remain in Sequencer64's JACK handling.

I'm not sure why Doxygen is applying the "code" font so often here. Weird, annoying.

3.2 JACK Functions

Please study the following URL and note these important points:

```
http://jackaudio.org/files/docs/html/transport-design.html
```

- The timebase master continuously updates position information, beats, timecode, etc. There is at most one master active at a time. If no client is registered as timebase master, frame numbers will be the only position information available.
- The timebase master registers a callback that updates position information while transport is rolling. Its output affects the following process cycle. This function is called immediately after the process callback in the same thread whenever the transport is rolling, or when any client has set a new position in the previous cycle.
- Clients that don't declare a sync callback are assumed ready immediately, anytime the transport wants to start. If a client doesn't require slow-sync processing, it can set its sync callback to NULL.
- The transport state is always valid; initially it is JackTransportStopped.
- When someone calls `jack_transport_start()`, the engine resets the poll bits and changes to a new state, JackTransportStarting.
- When all slow-sync clients are ready, the state changes to JackTransportRolling.

Does Sequencer64 need a latency callback?

```
http://jackaudio.org/files/docs/html/group__ClientCallbacks.html
```

(We need to see why most of the following is in a monospaced font. Is there a new Doxygen feature?)

Here are summaries of the JACK functions used in the jack_assistant module:

3.2.1 jack_client_open()

```
Open a client session with a JACK server. More complex and
powerful than <tt>jack_client_new()</tt>.
Clients choose which of several
servers to connect, and how to start the server automatically, if
not already running. There is also an option for JACK to generate
a unique client name.


  const char *   client_name,
  jack_options_t    options,
  jack_status_t *   status,
     ...
```

client_name of at most jack_client_name_size() characters. The name scope is local to each server. Unless forbidden by the JackUseExactName option, the server will modify this name to create a unique variant, if needed.

options formed by OR-ing together JackOptions bits. Only the JackOpenOptions bits are allowed.

status (if non-NULL) an address for JACK to return information from the open operation. This status word is formed by OR-ing together the relevant JackStatus bits.

Optional parameters: depending on corresponding [options bits] additional parameters may follow status (in this order).

[JackServerName] (char $*$) server_name selects from among several possible concurrent server instances. Server names are unique to each user. If unspecified, use "default" unless $JACK_DEFAULT_SERVER is defined in the process environment.

Returns:

Opaque client handle if successful. If this is NULL, the open operation failed, and $*$status includes JackFailure, and the caller is not a JACK client.

3.2.2 jack_on_shutdown()

```
Registers a function to call when the JACK server shuts down the
client thread. It must be an asynchonrous POSIX signal
handler: only async-safe functions, executed from another thread.
A typical function might set a flag or write to a pipe so that the
rest of the application knows that the JACK client thread has shut
down.  Clients do not need to call this function. It only helps
clients understand what is going on. It should be called before
<tt>jack_client_activate()</tt>.
```

3.2.3 jack_set_sync_callback()

```
Register/unregister as a slow-sync client; it can't respond
immediately to transport position changes.  The callback is run at
the first opportunity after registration: if the client is active,
this is the next process cycle, otherwise it is the first cycle
after <tt>jack_activate()</tt>.  After that, it runs as per
JackSyncCallback rules.  Clients that don't set this callback are
assumed ready immediately any time the transport wants to start.
```

3.2.4 jack_set_process_callback()

```
Tells the JACK server to call the callback whenever there is work.
The function must be suitable for real-time execution, it cannot
call functions that might block for a long time: malloc(), free(),
printf(), pthread_mutex_lock(), sleep(), wait(), poll(), select(),
pthread_join(), pthread_cond_wait(), etc.  In the current class,
this function is a do-nothing function.
```

3.2.5 jack_set_session_callback()

```
Tells the JACK server to call the callback when a session event is
delivered.  Setting more than one session callback per process is
probably a design error.  For a multiclient application, it's more
sensible to create a JACK client with only one session callback.
```

3.2.6 jack_activate()

```
Tells the JACK server that the application is ready to start
processing.
```

3.2.7 jack_release_timebase()

TODO

3.2.8 jack_client_close()

TODO

3.2.9 jack_transport_start()

```
Starts the JACK transport rolling.  Any client can make this
request at any time. It takes effect no sooner than the next
process cycle, perhaps later if there are slow-sync clients. This
function is realtime-safe.  No return code.
```

3.2.10 jack_transport_stop()

```
Starts the JACK transport rolling.  Any client can make this
request at any time.  This function is realtime-safe.  No return
code.
```

3.2.11 jack_transport_locate()

```
Repositions the transport to a new frame number.  May be called at
any time by any client. The new position takes effect in two
process cycles. If there are slow-sync clients and the transport is
already rolling, it will enter the JackTransportStarting state and
begin invoking their sync_callbacks until ready. This function is
realtime-safe.
```

3.2.12 jack_transport_reposition()

```
Request a new transport position.  May be called at any time by any
client. The new position takes effect in two process cycles. If
there are slow-sync clients and the transport is already rolling,
it will enter the JackTransportStarting state and begin invoking
their sync_callbacks until ready. This function is realtime-safe.
This call, made in the position() function, is currently disabled.
```

3.2.13 jack_transport_query()

Query the current transport state and position. This function is realtime-safe, and can be called from any thread. If called from the process thread, pos corresponds to the first frame of the current cycle and the state returned is valid for the entire cycle.

The first parameter is the client, which is a pointer to the JACK client structure.

The second parameter is a pointer to structure for returning current transport position; pos->valid will show which fields contain valid data. If pos is NULL, do not return position information.

This function returns the current transport state.

3.3 Modes Operation

3.3.1 No JACK, Live Mode

In ~/.config/sequencer64/sequencer64.rc, set:

- jack_transport = 0
- jack_master = 0
- jack_master_cond = 0
- jack_start_mode = 0

By changing the start mode to 0 (false), Sequencer64 is put into Live Mode. With this setting, control of the muting and unmuting of patterns resides in the main window (the patterns window). One can start the playback in the performance (song) window, but it will not affect which patterns play, at all.

Note that this option is part of the *File / Options / JACK/LASH* configuration page.

3.3.2 No JACK, Song Mode

In ~/.config/sequencer64/sequencer64.rc, set:

- jack_transport = 0
- jack_master = 0
- jack_master_cond = 0
- jack_start_mode = 1

By changing the start mode to 1 (true), Sequencer64 is put into Song Mode.

With this setting, control of the muting and unmuting of patterns resides in the song window (the performance window). The patterns shown in the pattern slots of the main window turn on and off whenever the progress bar is in the pattern as drawn in the perforance window.

Note that this option is part of the *File / Options / JACK/LASH* configuration page.

3.3.3 JACK Transport

In ~/.config/sequencer64/sequencer64.rc, set:

- jack_transport = 1
- jack_master = 0
- jack_master_cond = 0
- jack_start_mode = 0 or 1 (see previous section)

The current behavior is that qjackctl and sequencer64 playback/progress seem to be independent of each other.

The workaround seems to be to set seq24/sequencer64 as JACK Master, or if another *application* (e.g. Qtractor) is JACK Master.

OLD BEHAVIOR:

```
Start qjackctl, verify that it sets up correctly, then click it's
"play" button to start the transport rolling.  Run sequencer64, load a
file.  Then note that starting playback (whether in the main window or
in the performance window) is ineffective, but resets the time counter
in qjackctl.  Why?  With JACK sync enabled by the macro:

         [JACK transport slave]
         jack sync(): zero frame rate [single report]!?
         [JackTransportRolling]
         [JackTransportStarting]  (every time space bar pressed)
         [Start playback]
         . . .
```

END OF OLD BEHAVIOR.

3.4 Breakage

Old message about seq24 being broken:

http://lists.linuxaudio.org/pipermail/linux-audio-user/2010-November/073848.html

```
i dont see the transport synchronisation working with a jack1 svn version.
you are still using only a sync callback.

and you are relying on the transport to go through the
JackTransportStarting state.

this issue should be fixed.
iirc we came to the conclusion, that seq24 is broken, and we will not
revert the changes in jack, which break it.

the quick and dirty fix on your side, would be to register an empty
process_callback.

but the issue still remains. seq24 is NOT a slow sync client. but it
registers a sync_callback.
and it even takes a lock in the sync callback.

the patch for jack-session support didnt get merged either.
```

Another one (no need for a URL):

```
I use seq24 for the majority of my projects but it isn't ideal (I should
point out that I never finish anything). I don't like seq24's pianoroll
editor, the way you do CC envelopes isn't ideal, it uses alsa-midi, there's
unnecessary complexity in switching from pattern-trigger mode to song mode,
and its insistence on being transport master while not even being able to
adjust tempo when live is annoying
```

3.5 JACK References

- http://libremusicproduction.com/articles/demystifying-jack-%E2%80%93-beginners-guide
- http://jackaudio.org/files/docs/html/transport-design.html
- http://kxstudio.linuxaudio.org/Repositories

Chapter 4

User Testing of Sequencer64 with Yoshimi

Author(s) Chris Ahlstrom 2016-03-04

4.1 Introduction

This section describes user testing of Sequencer64 using Yoshimi. It will expand as we work our way through all the many use-cases that can be achieved with Sequencer64 and Yoshimi.

Please note that the most advanced and recent testing can be found currently in the document `contrib/notes/jack-testing.txt`. We will eventually merge the final tests here... someday.

4.2 Smoke Test

Every so often we run Sequencer64 with a software synthesizer to make sure we haven't broken any functionality via our major refactoring efforts. We call it a "smoke test". We fire up the two application, and see if anything smokes.

This smoke test sets up Yoshimi with a very simple ALSA setup, and no instruments are loaded. Instead, only the "Simple Sound" is used on all channels. We've been doing this test with Yoshimi 1.3.6. The current Debian Sid ("testing") version of Yoshimi is 1.3.6-2, pulled from SourceForge. It seems to have issues, so we've been cloning and pulling the code from:

```
https://github.com/Yoshimi/yoshimi.git
```

After getting the application build and installed, the next step is to run it, using ALSA for MIDI and for audio:

```
$ yoshimi -a -A &
```

Next, fix up the configuration files for Sequencer64, `~/.config/sequencer64/sequencer64.rc` and `~/.config/sequencer64/sequencer64.usr`.

First hide `sequencer64.usr` somewhere, or delete it, as it will determine what MIDI devices are available, and we don't want that (yet). Second, make sure that `sequencer64.rc` makes the following setting:

```
[manual-alsa-ports]

# Set to 1 if you want sequencer64 to create its own ALSA ports and
# not connect to other clients

0   # number of manual ALSA ports
```

Next, run the newly-built version of Sequencer64. If desired, use the –bus option described below to force the buss number to the buss you need, as shown in the second version of the command:

```
$ sequencer64/sequencer64 &
$ sequencer64/sequencer64 --bus 5 &
```

In *File / Options / MIDI Clock*, observe the MIDI inputs made available by your system. Our system shows:

```
[0] 14:0 (Midi Through Port-0)
[1] 128:0 (TiMidity port 0)
[2] 128:0 (TiMidity port 1)
[3] 128:0 (TiMidity port 2)
[4] 128:0 (TiMidity port 3)
[5] 129:0 (input)
```

For some reason (a bug in Yoshimi?), input "[5]" doesn't indicate that it is Yoshimi, but it is. Take note of that input number... that is the MIDI buss number that is needed to drive Yoshimi.

Also make sure that of the clock settings for those busses are "Off".

The next instruction still works, but it is easier to simply pass the option `–bus 5` to Sequencer64 when starting it up.

Now open the file `sequencer64/contrib/midi/b4uacuse-GM-format.midi` in Sequencer64. For all of the patterns (slots) that have lots of data in them, right click on the pattern and select *Midi Bus / [5] 129:0 (input)* and the desired channel number. (Doesn't matter much, just use up the lower channel numbers first).

Back in Yoshimi, select each Part corresponding to the channels you selected. Make sure *Enabled* is checked for each desired channel.

Back in Sequencer64, click on each pattern you want to hear, which highlights them in black. Now click the play button (green triangle). The song should play, with each part using the "Simple Sound". Not too bad for a bunch of sine waves, eh?

Now we can test the application more fully. Note that the instructions here are very light. Detailed instructions on the usage of Sequencer64 can be found in the following project, which contains a PDF file and the LaTeX code used to build it:

```
https://github.com/ahlstromcj/sequencer64-doc.git
```

Although it applies to an earlier version of the project, it still mostly holds true for Sequencer64.

4.3 Tests in the Patterns Window

The Patterns window is the inside portion of the main window, supported by the `mainwid` class. it contains a grid of boxes or slots, with each slot potentially containing a pattern, sequence, or track. Empty tracks (i.e. tracks that contain no events, like title-only tracks) are highlighted in yellow.

This window supports only a single variant of mouse-handling.

4.3.1 Button Clicks on a Pattern

A left-click on a pattern slot should cause the following to happen:

1. The pattern will be highlighted (white on a black background). This won't occur until the button is released.
2. During playback, the pattern will emit MIDI events and play its sequence.
3. If the pattern is dragged to another slot, whether playing is in progress or not, releasing the button in the destination slot will move the pattern to that slot.

A right-click on a pattern slot should cause the following to happen:

1. If the pattern is empty, then a pop-up menu to make a New pattern, paste a pattern, or make other selections will appear.
2. If the pattern is active, then a pop-up menu to Edit the pattern or make other selections will appear.
3. A second right-click, just off the menu, will dismiss the menu.

4.3.2 Patterns Window Key Shortcuts

First, note the selection of the File / Options / Keyboard / Show keys option. The tests here should work whether or not it is selected. The only difference is if the keys are shown.

We got a segfault during this test, when we weren't being systematic about it.

4.3.3 The Sequencer64 User File

To be discussed.

4.4 Tests Using Valgrind

Valgrind is a very useful tool for unearthing memory issues and other issues in an application, especially when one has the source code and can build the code with debugging information.

One runs the application from the command line, preceding its command line with valgrind and some of its options.

4.4.1 Valgrind Suppressions

One problem with valgrind is that it also uncovers errors in system libraries that one has no control over. These errors clutter the output, so we suppress them using a valgrind "suppressions" file. Here's how to create one:

```
$ valgrind --gen-suppressions=yes --log-file=val.supp ./Sequencer64/sequencer64
$ valgrind --gen-suppressions=all --log-file=val.supp ./Sequencer64/sequencer64
```

As the program runs, one is asked to print a suppression. If the error is due to a system or third-party library, answer "Y return", and then copy-and-paste the suppression to a file, giving it a name. For example, we provide a file `contrib/seq64.supp` containing suppressions of errors that annoy us. There are way too many "errors" in ALSA, GTK+, gtkmm, glibc, and more.

The second command collects all the suppressions. Passing the val.supp file through sed makes it immediately usable:

```
$ sed -i -e /^==/g val.supp
```

Running valgrind like this then shows mostly the errors we care about:

```
$ valgrind --suppressions=val.supp  ./Sequencer64/sequencer64
```

We've added some other suppression files to the `contrib` directory. Too much! For example:

https://github.com/dtrebbien/GNOME.supp

However, overall this process is very painful, and we're going to eventually do all the valgrind work on the unit-test project for Sequencer64:

https://github.com/ahlstromcj/seq64-tests

4.4.2 Full Valgrind Leak-Checking

Here's how to capture errors, while suppressing the system errors and while generating a log file:

```
$ valgrind --suppressions=contrib/seq64.supp --leak-check=full \
   --track-origins=yes --log-file=valgrind.log --show-leak-kinds=all \
   ./Sequencer64/sequencer64
```

The errors can be also be re-routed to a log-file via the "2> valgrind.log" shell redirection.

Another idea is to precede the valgrind command with the following construct:

```
$ G_SLICE=debug-blocks valgrind ...
```

G_SLICE=debug-blocks will turn off gtk's advanced memory management to allow valgrind to show correct results. This results in an amazing plethora or invalid read and invalid write errors in GNOME-related libraries. Sheesh!

And don't forget about Valgrind's "massif" memory-tracking tool! (More to come!)

4.4.2.1 Leak-Checking Basic Operation

For the first pass, just run Sequencer64, then immediately exit. Then scan the log file to see if any "errors" can be pinpointed to the application and library code.

Don't forget to run the same scenario without valgrind, in a console window, to see if any of our own debug/problem output occurs.

In any case, leakage tagged as "still reachable" isn't as bad as leakage tagged as "definitely lost" or "indirectly lost".

But good luck finding a Sequencer64 bug buried in the chaff of 3rd-party valgrind reports, even with some suppressions enabled. Apparently a lot of them have to do with data structures that are intended to last the full life of the application.

One can make the search a little easier by searching for the "seq64" namespace in the valgrind log.

4.5 Specific Fault Debugging

This section goes through specific debugging cases we encountered. They should be part of the regular testing of Sequencer64.

4.6 Snipping of a MIDI file.

In order to have a test file for the *seq64-tests* project, we loaded up the `b4uacuse-GM-format.midi` file, removed all but four of the tracks, and saved it as `b4uacuse-snipped.midi`. Loading this file into Sequencer64 caused the following:

```
   $ ./Sequencer64/sequencer64
[Reading user configuration /home/ahlstrom/.config/sequencer64/sequencer64.usr]
[Reading rc configuration /home/ahlstrom/.config/sequencer64/sequencer64.rc]
get_sequence(): m_seqs[4] not null
Segmentation fault
```

First step, fire up a debugger and see what happened. We use *cgdb* , a text-based front-end for gdb with a "vi" feel.

```
   $ cgdb ./Sequencer64/sequencer64
```

Just hit "r", do *File / Open* , navigate to `b4uacuse-snipped.midi`, select it, and watch what happens.

The "bt" (backtrace) command shows a pretty large stack, 52 items. Page up to the top of the stack, and select frame 1 ("fr 1"). This shows a mutex at a very low address, 0x650! Frame 2 shows we are in the automutex constructor, calling lock() on that same badly-located mutex. Frame 3 is in sequence::event_count(), same bad mutex, and the m_events member is at address 0x0. Obviously, we're dealing with an unallocated sequence.

Frame 4 is in mainwid::draw_sequence_on_pixmap(), just after we've retrieved the next sequence via perform↩ ::get_sequence(4). But that would be the fifth sequence (the sequence numbers start at 0), and we snipped all but 4 from the file before we saved it.

So, one thing we need to do is *check* the value returned by get_sequence() before we try to use it. The other thing to do is figure out how we got to the fifth sequence, and fix that code as well. Using the command "p perf().↩ sequence_count()", we verify that there are indeed only 4 sequences allocated.

Frame 5 is in mainwid::draw_sequences_on_pixmap(). That function tries to load all sequences on the current screen-set, from 0 to 31, without checking to see how many their actually are. Inefficient and dangerous.

Frame 6 is in mainwid::reset(). We could pass perf().sequence_count() here for checking, or get it in mainwid↩ ::draw_sequences_on_pixmap().

Before we fix this issue, we need to load a file that works, to see why it does not fail for most files. We will put a breakpoint at the top mainwid::draw_sequences_on_pixmap().

We hit the breakpoint before even loading a file, with a sequence_count() of 0. The call to valid_sequence(0) passes the test. We may want to make valid_sequence() take the sequence_count() into account. But the call to perf().is_active(0) prevents anything bad from happening at startup time.

Once we load a good file, the sequence_count() is 14 in mainwid::draw_sequences_on_pixmap(). We turn on the display of "offset" using the command "display offset", and "c" (for "continue") until offset = 14, which means we are beyond that last sequence. That bad access is prevented by perf().is_active(14).

So the fundamental problem is that perf().is_active(4) is not protecting the access when we load the "bad file". We need to find and fix that issue before papering over the problem with better access checks.

Start again, putting a breakpoint in the call to "new sequence(m_ppqn)" in midifile. This call sets up some members and clears the list of 256 playing notes. Add another breakpoint at "a_perf.add_sequence()" to see what's happening there.

What we find is that the first two tracks have proper sequence numbers as read from the MIDI file, 0 and 1. But the third one preserves the number from the old file, 4. We have a disjunction between the track number and the sequence number, a conceptual problem. We can leave it as is, and beef up the error-checking, or replace the sequence number with the track number when loading the file. What to do?

- Make sure that the is-active flag for all sequences is "false", that the pointers are always null, and make sure to test both of these items (depending on context) before doing anything with the sequence.
- Convert the sequence number to the track number upon saving the MIDI file, or upon reading the MIDI file, and use that number when adding the sequence to the perform object. This might affect some seq24/sequencer64 functionality, however. It's big move.

We need information on reading and importing.

First, if we look at a file that we created long ago by importing `b4uacuse.mid`, `b4uacuse-GM-format.↩ midi`, it has its fourteen sequence numbers identical to their track numbers. No problem.

Second, if we just read `b4uacuse.mid`, a non-seq24-created MIDI file, we see that each of its tracks have no sequence number – they are all zero. The perform::add_sequence() simple iterates from the beginning of m_seqs[] until it finds an inactive m_seqs[i], and uses that element to hold the sequence pointer.

But now it also segfaults! Let's fix all the non-checked get_sequence() calls right away, it is too big an issue to ignore.

In the end, we have to be aware that a screen-set can have blank (null) slots interspersed amongst the active slots.

Chapter 5

Licenses

Library This application and its libraries, sub-applications, and documents.

Author(s) Chris Ahlstrom 2015-09-10

5.1 License Terms for the This Project.

Wherever the tag $XPC_SUITE_GPL_LICENSE$ appears, or wherever reference to the GPL licensing scheme (any version) is mentioned, substitute the appropriate license text, depending on whether the project is a library, application, documentation, or server software. We're not going to include paragraphs of licensing information in every module; you are responsible for coming here to read the licensing information.

These licenses apply to each sub-project and file artifact in the project with which this license description was packaged.

Wherever the term **XPC** is encountered in this project, it refers to my projects, which go beyond the package that contains this document.

5.2 XPC Application License

The **XPC** application license is either the **GNU GPLv2**. or the **GNU GPLv3**. Generally, projects that originate with me use the latter language, while projects I have extended may specify the former license.

This program is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 3 of the License, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the

```
Free Software Foundation, Inc.
51 Franklin Street, Fifth Floor
Boston, MA 02110-1301, USA.
```

The text of the GNU GPL version 3 license can also be found here:

http://www.gnu.org/licenses/gpl-3.0.txt

5.3 XPC Library License

The **XPC** library license is the **GNU LGPLv3**.

5.4 XPC Documentation License

The **XPC** documentation license is the **GNU FDLv1.3**.

5.5 XPC Affero License

The **XPC** "Affero" license is the **GNU AGPLv3**.

At the present time, no **XPC** project uses the "Affero" license.

5.6 XPC License Summary

Include one of these licenses in your Doxygen documentation with one of the following Doxygen tags specified above:

```
\ref gpl_license_subproject
\ref gpl_license_application
\ref gpl_license_library
\ref gpl_license_documentation
\ref gpl_license_affero
```

For more information on navigating GNU licensing, see this page:

```
http://www.gnu.org/licenses/
```

Copies of these licenses (and some logos) are provided in the `licenses` directory of the main project (or you can search for them at *gnu.org*).

Chapter 6

Todo List

File calculations.cpp

There are additional user-interface and MIDI scaling variables in the perfroll module that we need to move here.

File perfnames.cpp

When bringing up this dialog, and starting play from it, some extra horizontal lines are drawn for some of the sequences. This happens even in seq24, so this is long standing behavior. Is it useful, and how? Where is it done? In perfroll?

Global seq64::editable_events::save_events ()

Consider what to do about the sequence::m_is_modified flag.

Global seq64::eventedit::handle_save ()

Could also support writing the events to a new sequence, for added flexibility.

Global seq64::mainwid::timeout ()

We should use this callback to display the current time in the playback.

Global seq64::mainwnd::mainwnd (perform &a_p, bool allowperf2=true, int ppqn=SEQ64_USE_DEFAUL↩ T_PPQN)

Offload most of the work into an initialization function like options does; make the perform parameter a reference; valgrind flags m_tooltips as lost data, but if we try to manage it ourselves, many more leaks occur.

Global seq64::mainwnd::on_key_release_event (GdkEventKey ∗a_ev)

Test this functionality in old and new application.

Global seq64::perfedit::perfedit (perform &p, bool second_perfedit=false, int ppqn=SEQ64_USE_DEFAU↩ LT_PPQN)

Offload most of the work into an initialization function like options does.

Global seq64::perform::add_sequence (sequence ∗seq, int perf)

Shouldn't we wrap around the sequence list if we can't find an empty sequence slot after prefnum?

Global seq64::perform::is_active (int seq) const

We should have the sequence object keep track of its own activity and access that via a reference or pointer.

Global seq64::perform::m_seqs [c_max_sequence]

First, make the sequence array a vector, and second, put allof these flags into a structure and access those members indirectly.

Global seq64::perform::set_left_tick (midipulse tick, bool setstart=true)

The perform::m_one_measure member is currently hardwired to PPQN ∗ 4.

Global seq64::perfroll::set_ppqn (int ppqn)

Resolve the issue of c_perf_scale_x versus m_perf_scale_x in perfroll.

Global seq64::perftime::set_ppqn (int ppqn)

We need make the 4 constant variable per the number of beats (quarter-notes) per bar, and also at least make 16 (4x4) a meaningful manifest constant.

Global seq64::pulses_to_string (midipulse p)

Still needs to be unit tested.

Global seq64::pulses_to_timestring (midipulse p, const midi_timing &timinginfo)

Still needs to be unit tested.

Global seq64::seqdata::on_scroll_event (GdkEventScroll *ev)

DOCUMENT the seqdata scrolling behavior in the documentation projects.

Global seq64::seqedit::get_measures ()

Create a sequence::set_units() function or a sequence::get_measures() function to forward to.

Global seq64::seqedit::seqedit (perform &perf, sequence &seq, int pos, int ppqn=SEQ64_USE_DEFAULT_PPQN)

Offload most of the work into an initialization function like options does.

Support the hightlight feature in one or both perfedit windows in the same way it is done in the mainwid.

Global seq64::seqmenu::m_modified

We need to make sure that the perform object is in control of the modification flag.

Global seq64::seqmenu::seq_clear_perf ()

All of seq_paste() can be offloaded to a (new) perform member function.

Global seq64::seqmenu::seq_copy ()

Can be offloaded to a perform member function that accepts a sequence clipboard non-const reference parameter.

Global seq64::seqmenu::seq_cut ()

A lot of seq_cut() can be offloaded to a (new) perform member function that takes a sequence clipboard non-const reference parameter.

Global seq64::seqmenu::seq_paste ()

All of seq_paste() can be offloaded to a (new) perform member function with a const clipboard reference parameter.

Global seq64::seqtime::update_pixmap ()

Sizing needs to be controlled by font parameters. Instead of 19 or 20, estimate the width of 3 letters. Instead of 9 pixels down, use the height of the seqtime and the height of a character.

Global seq64::sequence::get_minmax_note_events (int &lowest, int &highest)

For efficency, we should calculate this only when the event set changes, and save the results and return them if good.

Global seq64::sequence::stream_event (event &ev)

Consider adding a feature where event's are rejected if their channel doesn't match that of the sequence. This has been a complaint of some people. Would modify the add_event() and add_note() functions.

Global seq64::triggers::next (midipulse *tick_on, midipulse *tick_off, bool *selected, midipulse *tick_offset)

It would be a bit simpler to simply return a trigger object, wouldn't it?

Chapter 7

Deprecated List

Global seq64::clock_tick_duration_bogus (int bpm, int ppqn)

This is a somewhat bogus calculation used only for "statistical" output in the old perform module. Name changed to reflect this unfortunate fact. Use pulse_length_us() instead.

Global seq64::sequence::get_name () const

Chapter 8

Namespace Index

8.1 Namespace List

Here is a list of all namespaces with brief descriptions:

Chapter 9

Hierarchical Index

9.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

Chapter 10

Data Structure Index

10.1 Data Structures

Here are the data structures with brief descriptions:

Chapter 11

Namespace Documentation

11.1 Gtk Namespace Reference

11.2 seq64 Namespace Reference

Define this macro to use the new seq24 v.

Data Structures

- class AbstractPerfInput

  Provides an abstract base class to provide the minimal interface for the various "perf input" classes.
- class automutex

  Provides a mutex that locks automatically when created, and unlocks when destroyed.
- class click

  Encapsulates any possible mouse click.
- class condition_var

  A mutex works best in conjunction with a condition variable.
- class configfile

  This class is the abstract base class for optionsfile and userfile.
- class editable_event

  Provides for the management of MIDI editable events.
- class editable_events

  Provides for the management of an ordered collection MIDI editable events.
- class event

  Provides events for management of MIDI events.
- class event_list

  The event_list class is a receptable for MIDI events.
- class eventedit

  This class supports an Event Editor that is used to tweak the details of events and get a better idea of the mix of events in a sequence.
- class eventslots

  This class implements the left-side list of events in the pattern event-edit window.
- class font

  This class provides a wrapper for rendering fonts that are encoded as a 16 x 16 pixmap file in XPM format.

- class FruityPerfInput

  Implements the performance input of that certain fruity sequencer that people seem to like.
- struct FruitySeqEventInput

  This structure implements the interaction methods for the "fruity" mode of operation.
- class FruitySeqRollInput

  Implements the fruity mouse interaction paradigm for the seqroll.
- class gui_assistant

  This class provides an interface for some of the GUI support needed in Sequencer64.
- class gui_assistant_gtk2

  This class provides an interface for some of the Gtk/Gdk/Glib support needed in Sequencer64.
- class gui_drawingarea_gtk2

  Implements the basic drawing areas of the application.
- class gui_palette_gtk2

  Implements a stock palette of Gdk::Color elements.
- class gui_window_gtk2

  This class supports a basic interface for Gtk::Window-derived objects.
- class jack_assistant

  This class provides the performance mode JACK support.
- class jack_scratchpad

  Provide a temporary structure for passing data and results between a perform and jack_assistant object.
- struct jack_status_pair_t

  Provides an internal type to make it easier to display a specific and accurate human-readable message when a JACK operation fails.
- class keybindentry

  Class for management of application key-bindings.
- class keys_perform

  This class supports the performance mode.
- class keys_perform_gtk2

  This class supports the performance mode.
- struct keys_perform_transfer

  Provides a data-transfer structure to make it easier to fill in a keys_perform object's members using sscanf().
- class keystroke

  Encapsulates any practical keystroke.
- class lash

  This class supports LASH operations, if compiled with LASH support (i.e.
- class maintime

  This class provides the drawing of the progress bar at the top of the main window, along with two "pills" that move in time with the beat and measure.
- class mainwid

  This class implements the piano roll area of the application.
- class mainwnd

  This class implements the functionality of the main window of the application, except for the Patterns Panel functionality, which is implemented in the mainwid class.
- class mastermidibus

  The class that "supervises" all of the midibus objects?
- class midi_container

  This class is the abstract base class for a container of MIDI track information.
- class midi_control

  This class (formerly a struct) contains the control information for sequences that make up a live set.
- class midi_list

  This class is the std::list implementation of the midi_container.

- class midi_measures

  Provides a data structure to hold the numeric equivalent of the measures string "measures:beats:divisions" ("m:b:d").
- class midi_splitter

  This class handles the parsing and writing of MIDI files.
- class midi_timing

  We anticipate the need to have a small structure holding the parameters needed to calculate MIDI times within an arbitrary song.
- class midi_vector

  This class is the std::vector implementation of the midi_container.
- class midibus

  Provides a class for handling the MIDI buss on Linux.
- class midifile

  This class handles the parsing and writing of MIDI files.
- class mutex

  The mutex class provides a simple wrapper for the pthread_mutex_t type used as a recursive mutex.
- class options

  This class supports a full tabbed options dialog.
- class optionsfile

  Provides a file for reading and writing the application' main configuration file.
- class perfedit

  This class supports a Performance Editor that is used to arrange the patterns/sequences defined in the patterns panel.
- class perfnames

  This class implements the left-side keyboard in the patterns window.
- class perform

  This class supports the performance mode.
- struct performcallback

  Provides for notification of events.
- class perfroll

  This class implements the performance roll user interface.
- class perftime

  This class implements drawing the piano time at the top of the "performance window" (the "song editor").
- class rc_settings

  This class contains the options formerly named "global_xxxxxx".
- class rect

  A small helper class representing a rectangle.
- class Seq24PerfInput

  Implements the default (Seq24) performance input characteristics of this application.
- struct Seq24SeqEventInput

  This structure implement the normal interaction methods for Seq24.
- class seqdata

  This class supports drawing piano-roll eventis on a window.
- class seqedit

  Implements the Pattern Editor, which has references to:
- class seqevent

  Implements the piano event drawing area.
- class seqkeys

  This class implements the left side piano of the pattern/sequence editor.
- class seqmenu

  This class handles the right-click menu of the sequence slots in the pattern window.
- class seqroll

Implements the piano roll section of the pattern editor.

- class seqtime

  This class implements the piano time, whatever that is.
- class sequence

  The sequence class is firstly a receptable for a single track of MIDI data read from a MIDI file or edited into a pattern.
- class trigger

  This class hold a single trigger for a sequence object.
- class triggers

  The triggers class is a receptable the triggers that can be used with a sequence object.
- class user_instrument

  Provides data about the MIDI instruments, readable from the "user" configuration file.
- struct user_instrument_t

  This structure corresponds to `[user-instrument-N]` definitions in the `~/.seq24usr` or `~/.config/sequencer64/seq24usr` file.
- class user_midi_bus

  Provides data about the MIDI busses, readable from the "user" configuration file.
- struct user_midi_bus_t

  This structure corresponds to `[user-midi-bus-0]` definitions in the `~/.seq24usr` ("user") file (`~/.config/sequencer64/sequencer64.usr` in the latest version of the application).
- class user_settings

  Holds the current values of sequence settings and settings that can modify the number of sequences and the configuration of the user-interface.
- class userfile

  Supports the user's `~/.config/sequencer64/sequencer64.usr` and `~/.seq24usr` configuration file.

Typedefs

- typedef unsigned char midibyte

  Provides a fairly common type definition for a byte value.
- typedef unsigned char bussbyte

  Distinguishes a buss/bus number from other MIDI bytes.
- typedef unsigned short midishort

  Distinguishes a short value from the unsigned short values implicit in short-valued MIDI numbers.
- typedef unsigned long midilong

  Distinguishes a long value from the unsigned long values implicit in long-valued MIDI numbers.
- typedef long midipulse

  Distinguishes a long value from the unsigned long values implicit in MIDI time measurements.

Enumerations

Functions

- bool extract_timing_numbers (const std::string &s, std::string &part_1, std::string &part_2, std::string &part_3, std::string &fraction)

  Extracts up to 4 numbers from a colon-delimited string.
- std::string pulses_to_string (midipulse p)

  Converts MIDI pulses (also known as ticks, clocks, or divisions) into a string.
- std::string pulses_to_measurestring (midipulse p, const midi_timing &seqparms)

Converts a MIDI pulse/ticks/clock value into a string that represents "measures:beats:ticks" ("measures:beats:division").

- bool pulses_to_midi_measures (midipulse p, const midi_timing &seqparms, midi_measures &measures)

  Converts a MIDI pulse/ticks/clock value into a string that represents "measures:beats:ticks" ("measures:beats:division").
- std::string pulses_to_timestring (midipulse p, int bpm, int ppqn)

  Converts a MIDI pulse/ticks/clock value into a string that represents "hours:minutes:seconds.fraction".
- std::string pulses_to_timestring (midipulse p, const midi_timing &timinginfo)

  Converts a MIDI pulse/ticks/clock value into a string that represents "hours:minutes:seconds.fraction".
- midipulse measurestring_to_pulses (const std::string &measures, const midi_timing &seqparms)

  Converts a string that represents "measures:beats:division" to a MIDI pulse/ticks/clock value.
- midipulse midi_measures_to_pulses (const midi_measures &measures, const midi_timing &seqparms)

  Converts a string that represents "measures:beats:division" to a MIDI pulse/ticks/clock value.
- midipulse timestring_to_pulses (const std::string &timestring, int bpm, int ppqn)

  Converts a string that represents "hours:minutes:seconds.fraction" into a MIDI pulse/ticks/clock value.
- midipulse string_to_pulses (const std::string &s, const midi_timing &mt)

  Converts a time string to pulses.
- midibyte string_to_midibyte (const std::string &s)

  Converts a string to a MIDI byte.
- std::string shorten_file_spec (const std::string &fpath, int leng)

  Shortens a file-specification to make sure it is no longer than the provided length value.
- bool string_not_void (const std::string &s)

  Tests that a string is not empty and has non-space characters.
- bool string_is_void (const std::string &s)

  Tests that a string is empty or has only white-space characters.
- bool strings_match (const std::string &target, const std::string &x)

  Compares two strings for a form of semantic equality, for the purposes of editable_event(), for example.
- int log2_time_sig_value (int tsd)

  Calculates the log-base-2 value of a number that is already a power of 2.
- void tempo_to_bytes (midibyte t[3], int tempo_us)

  Provide a way to convert a tempo value (microseconds per quarter note) into the three bytes needed as value in a Tempo meta event.
- int zoom_power_of_2 (int ppqn)

  Calculates a suitable starting zoom value for the given PPQN value.
- double beats_per_minute_from_tempo (double tempo)

  This function calculates the effective beats-per-minute based on the value of a Tempo meta-event.
- double tempo_from_beats_per_minute (double bpm)

  This function is the inverse of beats_per_minute_from_tempo().
- double pulse_length_us (int bpm, int ppqn)

  Calculates pulse-length from the BPM (beats-per-minute) and PPQN (pulses-per-quarter-note) values.
- double delta_time_us_to_ticks (unsigned long us, int bpm, int ppqn)

  Converts delta time in microseconds to ticks.
- double ticks_to_delta_time_us (midipulse delta_ticks, int bpm, int ppqn)

  Converts the time in ticks ("clocks") to delta time in microseconds.
- double clock_tick_duration_bogus (int bpm, int ppqn)

  Calculates the duration of a clock tick based on PPQN and BPM settings.
- int clock_ticks_from_ppqn (int ppqn)

  A simple calculation to convert PPQN to MIDI clock ticks.
- double double_ticks_from_ppqn (int ppqn)

  A simple calculation to convert PPQN to MIDI clock ticks.
- midipulse measures_to_ticks (int bpm, int ppqn, int bw, int measures=1)

Calculates the length of an integral number of measures, in ticks.

- bool help_check (int argc, char ∗argv[ ])

  Checks to see if the first option is a help or version argument, just so we can skip the "Reading configuration ..." messages.
- bool parse_options_files (perform &p, int argc, char ∗argv[ ])

  Provides the command-line option support, as well as some setup support, extracted from the main routine of Sequencer64.
- int parse_command_line_options (int argc, char ∗argv[ ])

  Parses the command-line options on behalf of the application.
- bool write_options_files (const perform &p)

  Saves all options to the "rc" and "user" configuration files.
- std::string build_details ()

  Generates a string describing the features of the build.
- std::string to_string (const event &ev)

  A free function to convert an event into an informative string, just enough to save some debugging time.
- bool file_access (const std::string &targetfile, int mode)
- bool file_exists (const std::string &filename)

  Checks a file for existence.
- bool file_readable (const std::string &filename)

  Checks a file for readability.
- bool file_writable (const std::string &filename)

  Checks a file for writability.
- bool file_accessible (const std::string &filename)

  Checks a file for readability and writability.
- bool file_executable (const std::string &filename)

  Checks a file for the ability to be executed.
- bool file_is_directory (const std::string &filename)

  Checks a file to see if it is a directory.
- bool make_directory (const std::string &pathname)

  A function to ensure that the ∼/.config/sequencer64 directory exists.
- bool ppqn_is_valid (int ppqn)

  Common code for handling PPQN settings.
- int jack_sync_callback (jack_transport_state_t state, jack_position_t ∗pos, void ∗arg)

  Global functions for JACK support and JACK sessions.
- void jack_shutdown_callback (void ∗arg)

  This callback is to shutdown JACK by clearing the jack_assistant::m_jack_running flag.
- void jack_timebase_callback (jack_transport_state_t state, jack_nframes_t nframes, jack_position_t ∗pos, int new_pos, void ∗arg)

  The JACK timebase function defined here sets the JACK position structure.
- int jack_process_callback (jack_nframes_t nframes, void ∗arg)
- void jack_session_callback (jack_session_event_t ∗ev, void ∗arg)

  Set the m_jsession_ev (event) value of the perform object.
- std::string keyval_name (unsigned int key)

  Obtains the name of the key.
- void keyval_normalize (keys_perform_transfer &k)

  For the case in which the "rc" file is missing or corrupt, this function makes sure that each control key has a reasonable value.
- bool create_lash_driver (perform &p, int argc, char ∗∗argv)

  Creates and starts a lash object.
- lash ∗ lash_driver ()

  Provides access to the lash object.
- void delete_lash_driver ()

Deletes the last object.

- void * output_thread_func (void *p)

  Global functions defined in perform.cpp.
- void * input_thread_func (void *myperf)

  Set up the performance, and set the process to realtime privileges.
- long min (long a, long b)

  min() for long values.
- rc_settings & rc ()

  Returns a reference to the global rc_settings object.
- user_settings & usr ()

  Returns a reference to the global user_settings object, for better encapsulation.
- int choose_ppqn (int ppqn)

  Common code for handling PPQN settings.
- static std::string make_section_name (const std::string &label, int value)

  Provides a purely internal, ad hoc helper function to create numbered section names for the userfile class.
- font & font_render ()

  The p_font_renderer pointer was once created in the main module, sequencer64.cpp.
- Gtk::Adjustment & adjustment_dummy ()

  Provides a way to provide a dummy Gtk::Adjustment object, but not create one until it is actually needed, so that the Glib/Gtk infrastructure is ready for it.
- void update_mainwid_sequences ()

  This global function in the seq64 namespace calls mainwid :: update_sequences_on_window(), if the global mainwid object exists.
- void update_perfedit_sequences ()

  This global function in the seq64 namespace calls perfedit :: draw_sequences(), if the global perfedit objects exist.
- static long clamp (long val, long low, long hi)

  An internal function used by the FruitySeqRollInput class.
- static long clamp (long val, long low, long hi)

  An internal function used by the FruitySeqRollInput class.

Variables

- std::string c_controller_names [SEQ64_MIDI_COUNT_MAX]

  Provides the default names of MIDI controllers.
- const midibyte EVENT_STATUS_BIT

  This highest bit of the status byte is always 1.
- const midibyte EVENT_ANY

  Channel Voice Messages.
- const midibyte EVENT_NOTE_OFF
- const midibyte EVENT_NOTE_ON
- const midibyte EVENT_AFTERTOUCH
- const midibyte EVENT_CONTROL_CHANGE
- const midibyte EVENT_PROGRAM_CHANGE
- const midibyte EVENT_CHANNEL_PRESSURE
- const midibyte EVENT_PITCH_WHEEL
- const midibyte EVENT_MIDI_SYSEX

  System Messages.
- const midibyte EVENT_MIDI_QUARTER_FRAME
- const midibyte EVENT_MIDI_SONG_POS
- const midibyte EVENT_MIDI_SONG_SELECT
- const midibyte EVENT_MIDI_SONG_F4

- const midibyte EVENT_MIDI_SONG_F5
- const midibyte EVENT_MIDI_TUNE_SELECT
- const midibyte EVENT_MIDI_SYSEX_END
- const midibyte EVENT_MIDI_CLOCK
- const midibyte EVENT_MIDI_SONG_F9
- const midibyte EVENT_MIDI_START
- const midibyte EVENT_MIDI_CONTINUE
- const midibyte EVENT_MIDI_STOP
- const midibyte EVENT_MIDI_SONG_FD
- const midibyte EVENT_MIDI_ACTIVE_SENS
- const midibyte EVENT_MIDI_RESET
- const midibyte EVENT_MIDI_META

  0xFF is a MIDI "escape code" used in MIDI files to introduce a MIDI meta event.
- const midibyte EVENT_SYSEX

  A MIDI System Exclusive (SYSEX) message starts with F0, followed by the manufacturer ID (how many? bytes), a number of data bytes, and ended by an F7.
- const midibyte EVENT_SYSEX_END
- const midibyte EVENT_SYSEX_CONTINUE
- const midibyte EVENT_NULL_CHANNEL

  This value of 0xFF is Sequencer64's channel value that indicates that the event's m_channel value is bogus.
- const midibyte EVENT_GET_CHAN_MASK

  These file masks are used to obtain or to mask off the channel data from a status byte.
- const midibyte EVENT_CLEAR_CHAN_MASK
- const int c_midibus_output_size

  Manifest global constants.
- const int c_midibus_input_size

  The c_midibus_input_size value is passed, in mastermidibus, to snd_seq_set_input_buffer_size().
- const int c_midibus_sysex_chunk

  Controls the amount a SysEx data sent at one time, in the midibus module.
- const midilong c_midibus

  Provides tags used by the midifile class to control the reading and writing of the extra "proprietary" information stored in a Seq24 MIDI file.
- const midilong c_midich

  Track channel number.
- const midilong c_midiclocks

  Track clocking.
- const midilong c_triggers

  See c_triggers_new.
- const midilong c_notes

  Song data.
- const midilong c_timesig

  Track time signature.
- const midilong c_bpmtag

  Song beats/minute.
- const midilong c_triggers_new

  Track trigger data.
- const midilong c_mutegroups

  Song mute group data.
- const midilong c_midictrl

  Song MIDI control.
- const midilong c_musickey

  The track's key.

- const midilong c_musicscale

  The track's scale.
- const midilong c_backsequence

  Track background sequence.
- const int c_midi_track_ctrl

  Pseudo control values for associating MIDI events (I think) with automation of some of the controls in seq24.
- const int c_midi_control_bpm_up
- const int c_midi_control_bpm_dn
- const int c_midi_control_ss_up
- const int c_midi_control_ss_dn
- const int c_midi_control_mod_replace
- const int c_midi_control_mod_snapshot
- const int c_midi_control_mod_queue
- const int c_midi_control_mod_gmute
- const int c_midi_control_mod_glearn
- const int c_midi_control_play_ss
- const int c_midi_controls
- const bool c_scales_policy [c_scale_size][SEQ64_OCTAVE_SIZE]

  Each value in the kind of scale is denoted by a true value in these arrays.
- const int c_scales_transpose_up [c_scale_size][SEQ64_OCTAVE_SIZE]

  Increment values needed to transpose each scale up so that it remains in the same key.
- const int c_scales_transpose_dn [c_scale_size][SEQ64_OCTAVE_SIZE]

  Making these positive makes it easier to read, but the actual array contains negative values.
- const char c_scales_text [c_scale_size][20]

  The names of the currently-supported scales.
- const char c_key_text [SEQ64_OCTAVE_SIZE][4]

  Provides the entries for the Key dropdown menu in the Pattern Editor window.
- const char c_interval_text [16][4]

  Provides the entries for the Interval dropdown menu in the Pattern Editor window.
- const char c_chord_text [8][6]

  Provides the entries for the Chord dropdown menu in the Pattern Editor window.
- const int c_max_instruments

  Provides the maximum number of instruments that can be defined in the ~/.seq24usr or ~/.config/sequencer64/sequenc rc file.
- const int c_max_busses

  Provides the maximum number of MIDI buss definitions supported in the "user" file.
- static const std::string versiontext

  Sets up the "hardwired" version text for Sequencer64.
- static struct option long_options [ ]

  A structure for command parsing that provides the long forms of command-line arguments, and associates them with their respective short form.
- static const std::string s_arg_list

  Provides a complete list of the short options, and is passed to getopt_long().
- static const char *const s_help_1a

  Provides help text.
- static const char *const s_help_1b

  More help text.
- static const char *const s_help_2

  Still more help text.
- static const char *const s_help_3

  Still more help text.
- static const char *const s_help_4

Still more help text.

- static const std::string s_build_highlight_empty

  This section of variables provide static information about the options enabled or disabled during the build.
- static const std::string s_build_lash_support
- static const std::string s_build_jack_support
- static const std::string s_build_jack_session
- static const std::string s_build_pause_support
- static const std::string s_build_use_event_map
- static const std::string s_build_chord_generator
- static const std::string s_build_edit_highlight
- static const std::string s_build_timesig_tempo
- static const std::string s_build_midi_vector
- static const std::string s_build_solid_grid
- static const std::string s_build_follow_progress
- struct charpair_t s_character_mapping [ ]

  The array of mappings of the non-alphabetic characters.
- static lash * s_global_lash_driver

  The global pointer to the LASH driver instance.
- static const int c_status_replace

  Purely internal constants used with the functions that implement MIDI control for the application.
- static const int c_status_snapshot

  This value signals the "snapshot" functionality.
- static const int c_status_queue

  This value signals the "queue" functionality.
- static rc_settings g_rc_settings

  Provides the replacement for all of the other "global_xxx" variables.
- static user_settings g_user_settings

  Provides the replacement for all of the other settings in the "user" configuration file, plus some of the "constants" in the globals module.
- static const long s_handlesize

  An internal variable for handle size.
- static const int s_jitter_amount

  An internal variable for user-jitter control.
- static mainwid * gs_mainwid_pointer

  Holds a pointer to the single instance of mainwnd for the entire application, once it is created.
- const int c_mainwid_x

  The width of the main pattern/sequence grid, in pixels.
- const int c_mainwid_y
- static perfedit * gs_perfedit_pointer_0

  Holds a pointer to the first instance of perfedit for the entire application, once it is created.
- static perfedit * gs_perfedit_pointer_1

  Holds a pointer to the second instance of perfedit for the entire application, once it is created.
- static const int c_select_all_notes

  Actions.
- static const int c_select_all_events
- static const int c_select_inverse_notes
- static const int c_select_inverse_events
- static const int c_quantize_notes
- static const int c_quantize_events
- static const int c_tighten_events
- static const int c_tighten_notes
- static const int c_transpose_notes

- static const int c_reserved
- static const int c_transpose_h
- static const int c_swing_notes
- static const long s_handlesize

  An internal variable for handle size.

11.2.1 Detailed Description

0.9.3 delta-tick calculation code. This code doesn't quite work for generating the proper rate of MIDI clocks, and so have disabled that code until we can figure out what it is we're doing wrong. Do not enable it unless you are willing to test it.

11.2.2 Typedef Documentation

11.2.2.1 typedef unsigned char seq64::midibyte

11.2.2.2 typedef unsigned char seq64::bussbyte

11.2.2.3 typedef unsigned short seq64::midishort

11.2.2.4 typedef unsigned long seq64::midilong

11.2.2.5 typedef long seq64::midipulse

HOWEVER, CURRENTLY, if you make this value unsigned, then perfroll won't show any notes in the sequence bars!!! Also, a number of manipulations of this type currently depend upon it being a signed value.

11.2.3 Enumeration Type Documentation

11.2.3.1 enum seq64::seq_modifier_t

We have to tweak the names to avoid redeclaration errors and to "personalize" the values. We change "GDK" to "SEQ64".

Since we're getting events from, say Gtk-2.4, but using our (matching) values for comparison, use the CAST_EQ↩ UIVALENT() macro to compare them. Note that we might still end up having to a remapping (e.g. if trying to get the code to work with the Qt framework).

Enumerator

SEQ64_NO_MASK

SEQ64_SHIFT_MASK

SEQ64_LOCK_MASK

SEQ64_CONTROL_MASK

SEQ64_MOD1_MASK

SEQ64_MOD2_MASK

SEQ64_MOD3_MASK

SEQ64_MOD4_MASK
SEQ64_MOD5_MASK
SEQ64_BUTTON1_MASK
SEQ64_BUTTON2_MASK
SEQ64_BUTTON3_MASK
SEQ64_BUTTON4_MASK
SEQ64_BUTTON5_MASK
SEQ64_SUPER_MASK Bits 13 and 14 are used by XKB, bits 15 to 25 are unused. Bit 29 is used internally.
SEQ64_HYPER_MASK
SEQ64_META_MASK
SEQ64_RELEASE_MASK
SEQ64_MASK_MAX

11.2.3.2 enum seq64::seq_event_type_t

Only the values we need have been grabbed. We have to tweak the names to avoid redeclaration errors and to "personalize" the values. We change "GDK" to "SEQ64", but, for convenience (to hide errors? :-D), we keep the number the same.

Since we're getting events from, say Gtk-2.4, but using our (matching) values for comparison, use the CAST_EQ↩ UIVALENT() macro to compare them. Note that we might still end up having to a remapping (e.g. if trying to get the code to work with the Qt framework).

Enumerator

SEQ64_NOTHING
SEQ64_DELETE
SEQ64_DESTROY
SEQ64_EXPOSE
SEQ64_MOTION_NOTIFY
SEQ64_BUTTON_PRESS
SEQ64_2BUTTON_PRESS
SEQ64_3BUTTON_PRESS
SEQ64_BUTTON_RELEASE
SEQ64_KEY_PRESS
SEQ64_KEY_RELEASE
SEQ64_SCROLL
SEQ64_EVENT_LAST

11.2.3.3 enum seq64::seq_scroll_direction_t

We have to tweak the names to avoid redeclaration errors and to "personalize" the values. We change "SEQ64" to "SEQ64".

Since we're getting events from, say Gtk-2.4, but using our (matching) values for comparison, use the CAST_EQ↩ UIVALENT() macro to compare them. Note that we might still end up having to a remapping (e.g. if trying to get the code to work with the Qt framework).

Enumerator

SEQ64_SCROLL_UP
SEQ64_SCROLL_DOWN
SEQ64_SCROLL_LEFT
SEQ64_SCROLL_RIGHT

11.2.3.4 enum seq64::clock_e

This enumeration was also defined in midibus_portmidi.h, but we put it into this common module to avoid duplication.

Enumerator

e_clock_off Corresponds to the "Off" selection in the MIDI Clock tab. With this setting, the MIDI Clock is disabled for the buss using this setting. Notes will still be sent that buss, of course. Some software synthesizer might require this setting in order to make a sound.

e_clock_pos Corresponds to the "Pos" selection in the MIDI Clock tab. With this setting, MIDI Clock will be sent to this buss, and, if playback is starting beyond tick 0, then MIDI Song Position and MIDI Continue will also be sent on this buss.

e_clock_mod Corresponds to the "Mod" selection in the MIDI Clock tab. With this setting, MIDI Clock and MIDI Start will be sent. But clocking won't begin until the Song Position has reached the start modulo (in 1/16th notes) that is specified.

11.2.3.5 enum seq64::interaction_method_t

Moved here from the globals.h module.

Enumerator

e_seq24_interaction

e_fruity_interaction

e_number_of_interactions

11.2.3.6 enum seq64::c_music_scales

Scales can be shown in the piano roll as gray bars for reference purposes.

We've added three more scales; there are still a number of them that could be fruitfully added to the list of scales.

It would be good to offload this stuff into a new "scale" class.

Enumerator

c_scale_off

c_scale_major

c_scale_minor

c_scale_harmonic_minor

c_scale_melodic_minor

c_scale_c_whole_tone

c_scale_blues

c_scale_major_pentatonic

c_scale_minor_pentatonic

c_scale_size

11.2.3.7 enum seq64::draw_type

These values are used in the sequence, seqroll, perfroll, and mainwid classes.

Enumerator

DRAW_FIN Indicates that drawing is finished?

DRAW_NORMAL_LINKED Probably used for drawing linked notes.

DRAW_NOTE_ON For starting the drawing of a note?

DRAW_NOTE_OFF For finishing the drawing of a note?

11.2.3.8 enum seq64::mouse_action_e

Enumerator

e_action_select

e_action_draw

e_action_grow

11.2.4 Function Documentation

11.2.4.1 bool seq64::extract_timing_numbers (const std::string & *s*, std::string & *part_1*, std::string & *part_2*, std::string & *part_3*, std::string & *fraction*)

- measures : beats : divisions
  - "213:4:920"
  - "0:1:0"
- hours : minutes : seconds . fraction
  - "2:04:12.14"
  - "0:1:2"

Warning

This is not the most efficient implementation you'll ever see. At some point we will tighten it up. This function is tested in the seq64-tests project, in the "calculations_unit_test" module.

Parameters

	s	Provides the input time string, in measures or time format, to be processed.
out	*part_1*	The destination reference for the first part of the time.
out	*part_2*	The destination reference for the second part of the time.
out	*part_3*	The destination reference for the third part of the time.
out	*fraction*	The destination reference for the fractional part of the time.

Returns

Returns true if a reasonable portion (3 numbers) was good for extraction. The fraction part will start with a period for easier conversion to fractional seconds.

11.2.4.2 std::string seq64::pulses_to_string (midipulse *p*)

Todo Still needs to be unit tested.

Parameters

p	The MIDI pulse/tick value to be converted.

Returns

Returns the string as an unsigned ASCII integer number.

11.2.4.3 std::string seq64::pulses_to_measurestring (midipulse *p*, const midi_timing & *seqparms*)

Parameters

p	The number of MIDI pulses (clocks, divisions, ticks, you name it) to be converted. If the value is SEQ64_ILLEGAL_PULSE, it is converted to 0, because callers don't generally worry about such niceties, and the least we can do is convert illegal measure-strings (like "000:0:000") to a legal value.
seqparms	This small structure provides the beats/measure, beat-width, and PPQN that hold for the sequence involved in this calculation. These values are needed in the calculations

Returns

Returns the string, in measures notation, for the absolute pulses that mark this duration.

11.2.4.4 bool seq64::pulses_to_midi_measures (midipulse *p*, const midi_timing & *seqparms*, midi_measures & *measures*)

```
m = p * W / (4 * P * B)
```

Parameters

	p	Provides the MIDI pulses (as in "pulses per quarter note") that are to be converted to MIDI measures format.
	seqparms	This small structure provides the beats/measure (B), beat-width (W), and PPQN (P) that hold for the sequence involved in this calculation. The beats/minute (T for tempo) value is not needed.
out	*measures*	Provides the current MIDI song time structure to hold the results, which are the measures, beats, and divisions values for the time of interest. Note that the measures and beats are corrected to be re 1, not 0.

Returns

Returns true if the calculations were able to be made. The P, B, and W values all need to be greater than 0.

11.2.4.5 std::string seq64::pulses_to_timestring (midipulse *p*, int *bpm*, int *ppqn*)

If the fraction part is 0, then it is not shown. Examples:

```
-   "0:0:0"
-   "0:0:0.102333"
-   "12:3:1"
-   "12:3:1.000001"
```

Parameters

p	Provides the number of ticks, pulses, or divisions in the MIDI event time.
bpm	Provides the tempo of the song, in beats/minute.
ppqn	Provides the pulses-per-quarter-note of the song.

Returns

Returns the time-string representation of the pulse (ticks) value.

11.2.4.6 std::string seq64::pulses_to_timestring (midipulse *p*, const midi_timing & *timinginfo*)

See the other pulses_to_timestring() overload.

Todo Still needs to be unit tested.

Parameters

p	Provides the number of ticks, pulses, or divisions in the MIDI event time.
timinginfo	Provides the tempo of the song, in beats/minute, and the pulse-per-quarter-note of the song.

Returns

Returns the return-value of the other pulses_to_timestring() function.

11.2.4.7 midipulse seq64::measurestring_to_pulses (const std::string & *measures*, const midi_timing & *seqparms*)

Parameters

measures	Provides the current MIDI song time in "measures:beats:divisions" format, where divisions are the MIDI pulses in "pulses-per-quarter-note".
seqparms	This small structure provides the beats/measure, beat-width, and PPQN that hold for the sequence involved in this calculation.

Returns

Returns the absolute pulses that mark this duration. If the input string is empty, then 0 is returned.

11.2.4.8 midipulse seq64::midi_measures_to_pulses (const midi_measures & *measures,* const midi_timing & *seqparms*)

p = 4 ∗ P ∗ m ∗ B / W p == pulse count (ticks or pulses) m == number of measures B == beats per measure (constant) P == pulses per quarter-note (constant) W == beat width in beats per measure (constant)

Note that the 0-pulse MIDI measure is "1:1:0", which means "at the beginning of the first beat of the first measure, no pulses'. It is not "0:0:0" as one might expect.

Parameters

measures	Provides the current MIDI song time structure holding the measures, beats, and divisions values for the time of interest.
seqparms	This small structure provides the beats/measure, beat-width, and PPQN that hold for the sequence involved in this calculation.

Returns

Returns the absolute pulses that mark this duration. If the pulse-value cannot be calculated, then SEQ64_I↩ LLEGAL_PULSE is returned.

11.2.4.9 midipulse seq64::timestring_to_pulses (const std::string & *timestring,* int *bpm,* int *ppqn*)

Parameters

timestring	The time value to be converted, which must be of the form "hh:mm:ss" or "hh:mm:ss.fraction".
bpm	The beats-per-minute tempo (e.g. 120) of the current MIDI song.
ppqn	The parts-per-quarter note precision (e.g. 192) of the current MIDI song.

Returns

Returns 0 if an error occurred or if the number actually translated to 0.

This conversion assumes that the fractional parts of the seconds is padded with zeroes on the left or right to 6 digits.

This conversion assumes that the fractional parts of the seconds is padded with zeroes on the left or right to 6 digits.

11.2.4.10 midipulse seq64::string_to_pulses (const std::string & *s,* const midi_timing & *mt*)

First, the type of string is deduced by the characters in the string. If the string contains two colons and a decimal point, it is assumed to be a time-string ("hh:mm:ss.frac"); in addition ss will have to be less than 60.

If the string just contains two colons, then it is assumed to be a measure-string ("measures:beats:divisions").

If it has none of the above, it is assumed to be pulses. Testing is not rigorous.

Parameters

s	Provides the string to convert to pulses.
mt	Provides the structure needed to provide BPM and other values needed for some of the conversions done by this function.

Returns

Returns the string as converted to MIDI pulses (or divisions, clocks, ticks, whatever you call it).

11.2.4.11 midibyte seq64::string_to_midibyte (const std::string & *s*)

This function bypasses characters until it finds a digit (whether part of the number or a "0x" construct), and then converts it.

Parameters

s	Provides the string to convert to a MIDI byte.

Returns

Returns the MIDI byte value represented by the string.

11.2.4.12 std::string seq64::shorten_file_spec (const std::string & *fpath*, int *leng*)

This is done by removing character in the middle, if necessary, and replacing them with an ellipse.

This function operates by first trying to find the `/home` directory. If found, it strips off `/home/username` and replace it with the Linux ~ replacement for the `$HOME` environment variable. This function assumes that the "username" portion *must* exist, and that there's no goofy stuff like double-slashes in the path.

Parameters

fpath	The file specification, including the full path to the file, and the name of the file.
leng	Provides the length to which to limit the string.

Returns

Returns the fpath parameter, possibly shortened to fit within the desired length.

11.2.4.13 bool seq64::string_not_void (const std::string & *s*)

Provides essentially the opposite test that string_is_void() provides. The definition of white-space is provided by the std::isspace() function/macro.

Parameters

s	The string pointer to check for emptiness.

Returns

Returns true if the pointer is valid, the string has a non-zero length, and is not just white-space.

11.2.4.14 bool seq64::string_is_void (const std::string & *s*)

Meant to have essentially the opposite result of string_not_void(). The meaning of empty is special here, as it refers to a string being useless as a token:

- The string is of zero length.
- The string has only white-space characters in it, where the isspace() macro provides the definition of white-space.

Parameters

s	The string pointer to check for emptiness.

Returns

Returns true if the string has a zero length, or is only white-space.

11.2.4.15 bool seq64::strings_match (const std::string & *target,* const std::string & *x*)

The strings_match() function returns true if the comparison items are identical, without case-sensitivity in character content up to the length of the secondary string. This allows abbreviations to match. (And, in scanning routines, the first match is immediately accepted.)

Parameters

target	The primary string in the comparison. This is the target string, the one we hope to match. It is *assumed* to be non-empty, and the result is false if it is empty..
x	The secondary string in the comparison. It must be no longer than the target string, or the match is false.

Returns

Returns true if both strings are are identical in characters, up to the length of the secondary string, with the case of the characters being insignificant. Otherwise, false is returned.

11.2.4.16 int seq64::log2_time_sig_value (int *tsd*)

Useful in converting a time signature's denominator to a Time Signature meta event's "dd" value.

Parameters

tsd	The time signature denominator, which must be a power of 2: 2, 4, 8, 16, or 32.

Returns

Returns the power of 2 that achieves the *tsd* parameter value.

11.2.4.17 void seq64::tempo_to_bytes (midibyte *t[3],* int *tempo_us*)

Recall the format of a Tempo event:

0 FF 51 03 t2 t1 t0 (tempo as number of microseconds per quarter note)

This code is the inverse of the lines of code around line 768 in midifile.cpp, which is basically `((t2 * 256) + t1) * 256 + t0` .

As a test case, note that the default tempo is 120 beats/minute, which is equivalent to tttttt=500000 (0x07A120).

Parameters

t	Provides a small array of 3 elements to hold each tempo byte.
tempo_us	Provides the temp value in microseconds per quarter note.

11.2.4.18 int seq64::zoom_power_of_2 (int *ppqn*)

The default starting zoom is 2, but this value is suitable only for PPQN of 192 and below. Also, zoom currently works consistently only if it is a power of 2. For starters, we scale the zoom to the selected ppqn, and then shift it each way to get a suitable power of two.

Parameters

ppqn	The ppqn of interest.

Returns

Returns the power of 2 appropriate for the given PPQN value.

11.2.4.19 double seq64::beats_per_minute_from_tempo (double *tempo*) [inline]

The tempo event's numeric value is given in 3 bytes, and is in units of microseconds-per-quarter-note (us/qn).

Parameters

tempo	The value of the Tempo meta-event, in units of us/qn. If this value is 0, we'll get an arithmetic exception.

Returns

Returns the beats per minute. If the tempo value is too small, then this function will crash. :-D

11.2.4.20 double seq64::tempo_from_beats_per_minute (double *bpm*) [inline]

Parameters

bpm	The value of beats-per-minute. If this value is 0, we'll get an arithmetic exception.

Returns

Returns the tempo in qn/us. If the bpm value is too small, then this function will crash. :-D

11.2.4.21 double seq64::pulse_length_us (int *bpm,* int *ppqn*) [inline]

The formula for the pulse-length in seconds is:

```
          60
P = ------------
     BPM * PPQN
```

Parameters

bpm	Provides the beats-per-minute value. No sanity check is made. If this value is 0, we'll get an arithmetic exception.
ppqn	Provides the pulses-per-quarter-note value. No sanity check is made. If this value is 0, we'll get an arithmetic exception.

Returns

Returns the pulse length in microseconds. If either parameter is invalid, then this function will crash. :-D

11.2.4.22 double seq64::delta_time_us_to_ticks (unsigned long *us,* int *bpm,* int *ppqn*) [inline]

This function is the inverse of ticks_to_delta_time_us().

Please note that terms "ticks" and "pulses" are equivalent, and refer to the "pulses" in "pulses per quarter note".

```
          beats       pulses           1 minute       1 sec
P = 120 ------ * 192 ------ * T us *  ---------  * ---------
        minute       beats            60 sec       1,000,000 us
```

```
Note that this formula assumes that a beat is a quarter note.  If a beat
is an eighth note, then the P value would be halved, because there would
be only 96 pulses per beat.  We will implement an additional function to
account for the beat; the current function merely blesses some
calculations made in the application.
```

Parameters

us	The number of microseconds in the delta time.
bpm	Provides the beats-per-minute value, otherwise known as the "tempo".
ppqn	Provides the pulses-per-quarter-note value, otherwise known as the "division".

Returns

Returns the tick value.

11.2.4.23 double seq64::ticks_to_delta_time_us (midipulse *delta_ticks,* int *bpm,* int *ppqn*) [inline]

The inverse of delta_time_us_to_ticks().

Please note that terms "ticks" and "pulses" are equivalent, and refer to the "pulses" in "pulses per quarter note".

Old: 60000000.0 ∗ double(delta_ticks) / (double(bpm) ∗ double(ppqn));

Parameters

delta_ticks	The number of ticks or "clocks".
bpm	Provides the beats-per-minute value, otherwise known as the "tempo".
ppqn	Provides the pulses-per-quarter-note value, otherwise known as the "division".

Returns

Returns the time value in microseconds.

11.2.4.24 double seq64::clock_tick_duration_bogus (int *bpm,* int *ppqn*) [inline]

Deprecated This is a somewhat bogus calculation used only for "statistical" output in the old perform module. Name changed to reflect this unfortunate fact. Use pulse_length_us() instead.

$$us = \frac{60000000 \text{ ppqn}}{\text{MIDI\_CLOCK\_IN\_PPQN} * bpm * ppqn}$$

MIDI_CLOCK_IN_PPQN is 24.

Parameters

bpm	Provides the beats-per-minute value. No sanity check is made. If this value is 0, we'll get an arithmetic exception.
ppqn	Provides the pulses-per-quarter-note value. No sanity check is made. If this value is 0, we'll get an arithmetic exception.

Returns

Returns the clock tick duration in microseconds. If either parameter is invalid, this will crash. Who wants to waste time on value checks here? :-D

11.2.4.25 int seq64::clock_ticks_from_ppqn (int *ppqn*) [inline]

Parameters

ppqn	The number of pulses per quarter note. For example, the default value for Seq24 is 192.

Returns

The integer value of ppqn / 24 [MIDI_CLOCK_IN_PPQN] is returned.

11.2.4.26 double seq64::double_ticks_from_ppqn (int *ppqn*) [inline]

The same as clock_ticks_from_ppqn(), but returned as a double float.

Parameters

ppqn	The number of pulses per quarter note.

Returns

The double value of ppqn / 24 [SEQ64_MIDI_CLOCK_IN_PPQN]_is returned.

11.2.4.27 midipulse seq64::measures_to_ticks (int *bpm,* int *ppqn,* int *bw,* int *measures* = 1) [inline]

This function is called in seqedit::apply_length(), when the user selects a sequence length in measures. That function calculates the length in ticks. The number of pulses is given by the number of quarter notes times the pulses per quarter note. The number of quarter notes is given by the measures times the quarter notes per measure. The quarter notes per measure is given by the beats per measure times 4 divided by beat_width beats. So:

```
p = 4 * P * m * B / W
    p == pulse count (ticks or pulses)
    m == number of measures
    B == beats per measure (constant)
    P == pulses per quarter-note (constant)
    W == beat width in beats per measure (constant)

For our "b4uacuse" MIDI file, M can be about 100 measures, B is 4,
P can be 192 (but we want to support higher values), and W is 4.
So p = 100 * 4 * 4 * 192 / 4 = 76800 ticks.  Seems small.
```

Parameters

bpm	The B value in the equation, beats/measure.
ppqn	The P value in the equation, pulses/qn.
bw	The W value in the equation, the denominator of the time signature. If this value is 0, we'll get an arithmetic exception (crash), so we just return 0 in this case..
measures	The M value in the equation. It defaults to 1, in case one desires a simple "ticks per measure" number.

Returns

Returns the L value (ticks or pulses) as calculated via the given equation. If bw is 0, then 0 is returned.

11.2.4.28 bool seq64::help_check (int *argc*, char * *argv[ ]*)

Also check for the –legacy option. Finally, it also checks for the "?" option that people sometimes use as a guess to get help.

Parameters

argc	The number of command-line arguments.
argv	The array of command-line argument pointers.

Returns

Returns true only if -V, –version, -h, –help, or "?" were encountered. If the legacy options occurred, then rc().legacy_format(true) is called, as a side effect, because it will be needed before we parse the options.

11.2.4.29 bool seq64::parse_options_files (perform & *p*, int *argc*, char * *argv[ ]*)

It probably requires this call preceding: Gtk::Main kit(argc, argv), to strip any GTK+-specific parameters the knowledgeable user may have added. Usage:

```
Gtk::Main kit(argc, argv);
seq64::gui_assistant_gtk2 gui;
seq64::perform p(gui);
```

It also requires the caller to call rc().set_defaults() and usr().set_defaults(). The caller can then use the command-line to make any modifications to the setting that will be used here. The biggest example is the -r/–reveal-alsa-ports option, which determines if the MIDI buss definition strings are read from the 'user' configuration file.

Instead of the legacy Seq24 names, we use the new configuration file-names, located in the ~/.config/sequencer64 directory. However, if they are not found, we no longer fall back to the legacy configuration file-names. If the –legacy option is in force, use only the legacy configuration file-name. The code also ensures the directory exists. CURRENTLY LINUX-SPECIFIC. See the rc_settings class for how this works.

```
std::string cfg_dir = seq64::rc().home_config_directory();
if (cfg_dir.empty())
    return EXIT_FAILURE;
```

Change Note ca 2016-04-03 We were parsing the user-file first, but we now need to parse the rc-file first, to get the manual-alsa-ports option, so that we can avoid overriding the port names that the ALSA system provides, if the manual-alsa-option is false.

Parameters

p	Provides the perform object that will be affected by the new parameters.
argc	The number of command-line arguments.
argv	The array of command-line argument pointers.

Returns

Returns true if the reading of both configuration files succeeded.

11.2.4.30 int seq64::parse_command_line_options (int *argc,* char * *argv[ ]*)

Note that, since we call this function twice (once before the configuration files are parsed, and once after), we have to make sure that the global value optind is reset to 0 before calling this function. Note that the traditional reset value for optind is 1, but 0 is used in GNU code to trigger the internal initialization routine of get_opt().

Parameters

argc	The number of command-line arguments.
argv	The array of command-line argument pointers.

Returns

Returns the value of optind if no help-related options were provided.

11.2.4.31 bool seq64::write_options_files (const perform & *p*)

This function gets any legacy global variables, on the theory that they might have been changed.

Parameters

p	Provides the perform object that may provide new values for the parameters.

Returns

Returns true if both files were saved successfully. Otherwise returns false. But even if one write failed, the other might have succeeded.

11.2.4.32 std::string seq64::build_details ( )

Returns

Returns an ordered, human-readable string enumerating the features.

11.2.4.33 std::string seq64::to_string (const event & *ev*)

Nothing fancy. If you want that, use the midicvt project.

Parameters

ev	The event to put on show.

Returns

Returns the string representation of the event parameter.

11.2.4.34 bool seq64::file_access (const std::string & *targetfile,* int *mode*)

11.2.4.35 bool seq64::file_exists (const std::string & *filename*)

Parameters

filename	Provides the name of the file to be checked.

Returns

Returns 'true' if the file exists.

11.2.4.36 bool seq64::file_readable (const std::string & *filename*)

Parameters

filename	Provides the name of the file to be checked.

Returns

Returns 'true' if the file is readable.

11.2.4.37 bool seq64::file_writable (const std::string & *filename*)

Parameters

filename	Provides the name of the file to be checked.

Returns

Returns 'true' if the file is writable.

11.2.4.38 bool seq64::file_accessible (const std::string & *filename*)

An even stronger test than file_exists. At present, we see no need to distinguish read and write permissions. We assume the file is accessible only if the file has both permissions.

Parameters

filename	Provides the name of the file to be checked.

Returns

Returns 'true' if the file is readable and writable.

11.2.4.39 bool seq64::file_executable (const std::string & *filename*)

Parameters

filename	Provides the name of the file to be checked.

Returns

Returns 'true' if the file exists.

11.2.4.40 bool seq64::file_is_directory (const std::string & *filename*)

This function is also used in the function of the same name in fileutilities.cpp.

Parameters

filename	Provides the name of the directory to be checked.

Returns

Returns 'true' if the file is a directory.

11.2.4.41 bool seq64::make_directory (const std::string & *pathname*)

This function is actually a little more general than that, but it is not sufficiently general, in general.

Parameters

pathname	Provides the name of the path to create. The parent directory of the final directory must already exist.

Returns

Returns true if the path-name exists.

11.2.4.42 bool seq64::ppqn_is_valid (int *ppqn*) [inline]

Validates a PPQN value.

Parameters

ppqn	Provides the PPQN value to be used.

Returns

Returns true if the ppqn parameter is between MINIMUM_PPQN and MAXIMUM_PPQN, or is set to SE↩ Q64_USE_DEFAULT_PPQN (-1).

11.2.4.43 int seq64::jack_sync_callback (jack_transport_state_t *state*, jack_position_t * *pos*, void * *arg*)

This JACK synchronization callback informs the specified perform object of the current state and parameters of JACK.

The transport state will be:

```
-   JackTransportStopped when a new position is requested.
-   JackTransportStarting when the transport is waiting to start.
-   JackTransportRolling when the timeout has expired, and the
    position is now a moving target.
```

Parameters

state	The JACK Transport state.
pos	The JACK position value.
arg	The pointer to the jack_assistant object. Currently not checked for nullity, nor dynamic-casted.

Returns

Returns 1 if the function works, and 0 if something was wrong.

11.2.4.44 void seq64::jack_shutdown_callback (void * *arg*)

Parameters

arg	Points to the jack_assistant in charge of JACK support for the perform object.

11.2.4.45 void seq64::jack_timebase_callback (jack_transport_state_t *state*, jack_nframes_t *nframes*, jack_position_t * *pos*, int *new_pos*, void * *arg*)

The original version of the function worked properly with Hydrogen, but not with Klick. The new code seems to work with both. More testing and clarification is needed. This new code was "discovered" in the source-code for the "SooperLooper" project:

```
http://essej.net/sooperlooper/
```

The first difference with the new code is that it handles the case where the JACK position is moved (new_pos == true). If this is true, and the JackPositionBBT bit is off in pos->valid, then the new BBT value is set.

The seconds set of differences are in the "else" clause. In the new code, it is very simple: calculate the new tick value, back it off by the number of ticks in a beat, and perhaps go to the first beat of the next bar.

In the old code (complex!), the simple BBT adjustment is always made. This changes (perhaps) the beats_per_bar, beat_type, etc. We need to make these settings use the actual global values for beats set for Sequencer64. Then, if transitioning from JackTransportStarting to JackTransportRolling (instead of checking new_pos!), the BBT values (bar, beat, and tick) are finally adjusted. Here are the steps, with old and new steps noted:

```
-#  Calculate the "delta" ticks based on the current frame, the
    ticks_per_beat, the beats_per_minute, and the frame_rate.  The old
    code saves this in a local, the new code assigns it to pos->tick.
-#  Old code: save this delta as a positive value.
-#  Figure out the settings and modify bar, beat, tick, and
    bar_start_tick.  The old and new code seem to have the same intent,
    but it seems like the new code is faster and also correct.
    -   Old code:  Calculations are made by division and mod
        operations.
    -   New code:  Calculations are made by increments and decrements
        in a while loop.
```

Parameters

state	Indicates the current state of JACK transport.
nframes	The number of JACK frames in the current time period.
pos	Provides the position structure to be filled in, the address of the position structure for the next cycle; pos->frame will be its frame number. If new_pos is FALSE, this structure contains extended position information from the current cycle. If TRUE, it contains whatever was set by the requester. The timebase_callback's task is to update the extended information here.
new_pos	TRUE (non-zero) for a newly requested pos, or for the first cycle after the timebase_callback is defined. This is usually 0 in Sequencer64 at present, and 1 if one, say, presses "rewind" in qjackctl.
arg	Provides the jack_assistant pointer, currently unchecked for nullity.

11.2.4.46 int seq64::jack_process_callback (jack_nframes_t *nframes*, void * *arg*)

11.2.4.47 void seq64::jack_session_callback (jack_session_event_t * *ev*, void * *arg*)

Glib is then used to connect in perform::jack_session_event(). However, the perform object's GUI-support interface is used instead of the following, so that the libseq64 library can be independent of a specific GUI framework:

```
Glib::signal_idle().
    connect(sigc::mem_fun(*jack, &jack_assistant::session_event));
```

Parameters

ev	The JACK event to be set.
arg	The pointer to the jack_assistant object. Currently not checked for nullity.

11.2.4.48 std::string seq64::keyval_name (unsigned int *key*)

In gtkmm, this is done via the gdk_keyval_name() function. Here, in the base class, we just provide an easy-to-create string. Note that this is a free function, not a class member.

Parameters

key	Provides the key-number to be converted to a key name.

Returns

Returns the key name as looked up by the GDK infrastructure. If the key is not found, then an empty string is returned.

11.2.4.49 void seq64::keyval_normalize (keys_perform_transfer & *k*)

Otherwise, random values, unchecked, can cause the application to crash.

Any field that is 0 or greater than 65536 is fixed. Not perfect, but better than allowing random values to be used.

Parameters

k	The structure to be validated and normalized.

11.2.4.50 bool seq64::create_lash_driver (perform & *p,* int *argc,* char ∗∗ *argv*)

Initializes the lash driver (strips lash-specific command line arguments), then connects to the LASH daemon and polls events.

This function will always be called from the main routine, and called only once. Note that we don't need that darn SEQ64_LASH_SUPPORT macro in client code anymore.

Parameters

p	The perform object that needs to implement LASH support.
argc	The number of command-line arguments.
argv	The command-line arguments.

Returns

This function returns true if a lash object was created. This function will not create one in not configured to, if the command-line options did not specify the creation of the LASH driver, or if the LASH driver was already created.

11.2.4.51 lash ∗ seq64::lash_driver ( )

Returns

Returns the pointer to the LASH driver if it exists. Otherwise a null pointer is returned. The caller *must always check* the return value.

11.2.4.52 void seq64::delete_lash_driver ( )

This function will always be called from the main routine, once. The other lash-pointer functions will know if the pointer has been deleted.

11.2.4.53 void ∗ seq64::output_thread_func (void ∗ *myperf*)

Set up the performance, set the process to realtime privileges, and then start the output function.

Parameters

myperf	Provides the perform object instance that is to be used. Its output_func() is called. Currently, this parameter is not validated, for speed.

Returns

Always returns nullptr.

11.2.4.54 void * seq64::input_thread_func (void * *myperf*)

Parameters

myperf	Provides the perform object instance that is to be used. Its output_func() is called. Currently, this parameter is not validated, for speed.

Returns

Always returns nullptr.

11.2.4.55 long seq64::min (long *a,* long *b*) [inline]

Parameters

a	First operand.
b	Second operand.

Returns

Returns the minimum value of a and b.

11.2.4.56 rc_settings& seq64::rc ( )

Why a function instead of direct variable access? Encapsulation. We are then free to change the way "global" settings are accessed, without changing client code.

Returns

Returns the global object g_rc_settings.

11.2.4.57 user_settings& seq64::usr ( )

Returns

Returns the global object g_user_settings.

11.2.4.58 int seq64::choose_ppqn (int *ppqn*)

Putting it here means we can reduce the reliance on the global ppqn.

Parameters

ppqn	Provides the PPQN value to be used.

Returns

Returns the ppqn parameter, unless that parameter is SEQ64_USE_DEFAULT_PPQN (-1), then usr().midi_ppqn is returned.

11.2.4.59 static std::string seq64::make_section_name (const std::string & *label*, int *value*) [static]

Parameters

label	The base-name of the section.
value	The numeric value to append to the section name.

Returns

Returns a string of the form "[basename-1]".

11.2.4.60 font& seq64::font_render ( ) [inline]

We've going to render this pointer obsolete, though, and use a smart factory function to ensure the existence of this pointer, and return a reference to the font object.

We wanted to make the font a const object, but mainwid::on_realize() calls the font::init() function with its window object, and using const is impractical. We don't want to force every caller to deal with the overhead of passing even a null window pointer, either.

However, at some point we need some quarantee that the init() function is called before rendering a string. Right now, we guarantee it only by build order.

Returns

Returns a reference to the object pointed to by sp_font_renderer.

11.2.4.61 Gtk::Adjustment & seq64::adjustment_dummy ( )

This static object is used so we have an Adjustment to assign to the Adjustment members for classes that don't use them. Clumsy? We shall see.

Anyway, the parameters for this constructor are value, lower, upper, step-increment, and two more values.

11.2.4.62 void seq64::update_mainwid_sequences ( )

It is used by other objects that can modify the currently-edited sequence shown in the mainwid (main window).

11.2.4.63 void seq64::update_perfedit_sequences ( )

It is used by other objects (seqedit and eventedit) that can modify the currently-edited sequence shown in the perfedit (song window).

11.2.4.64 static long seq64::clamp (long *val,* long *low,* long *hi*) [inline],[static]

11.2.4.65 static long seq64::clamp (long *val,* long *low,* long *hi*) [inline],[static]

11.2.5 Variable Documentation

11.2.5.1 std::string seq64::c_controller_names

This array is used only by the seqedit class.

11.2.5.2 const midibyte seq64::EVENT_STATUS_BIT

11.2.5.3 const midibyte seq64::EVENT_ANY

The following MIDI events are channel messages. The comments represent the one or two data-bytes of the message.

Note that Channel Mode Messages use the same code as the Control Change, but uses reserved controller numbers ranging from 122 to 127.

The EVENT_ANY (0x00) value may prove to be useful in allowing any event to be dealt with. Not sure yet, but the cost is minimal.

11.2.5.4 const midibyte seq64::EVENT_NOTE_OFF

11.2.5.5 const midibyte seq64::EVENT_NOTE_ON

11.2.5.6 const midibyte seq64::EVENT_AFTERTOUCH

11.2.5.7 const midibyte seq64::EVENT_CONTROL_CHANGE

11.2.5.8 const midibyte seq64::EVENT_PROGRAM_CHANGE

11.2.5.9 const midibyte seq64::EVENT_CHANNEL_PRESSURE

11.2.5.10 const midibyte seq64::EVENT_PITCH_WHEEL

11.2.5.11 const midibyte seq64::EVENT_MIDI_SYSEX

The following MIDI events have no channel. We have included redundant constant variables for the SysEx Start and End bytes just to make it clear that they are part of this sequence of values, though usually treated separately.

Only the following constants are followed by some data bytes:

```
-   EVENT_MIDI_SYSEX            = 0xF0
-   EVENT_MIDI_QUARTER_FRAME    = 0xF1      // undefined?
-   EVENT_MIDI_SONG_POS         = 0xF2
-   EVENT_MIDI_SONG_SELECT      = 0xF3
```

11.2.5.12 const midibyte seq64::EVENT_MIDI_QUARTER_FRAME

11.2.5.13 const midibyte seq64::EVENT_MIDI_SONG_POS

11.2.5.14 const midibyte seq64::EVENT_MIDI_SONG_SELECT

11.2.5.15 const midibyte seq64::EVENT_MIDI_SONG_F4

11.2.5.16 const midibyte seq64::EVENT_MIDI_SONG_F5

11.2.5.17 const midibyte seq64::EVENT_MIDI_TUNE_SELECT

11.2.5.18 const midibyte seq64::EVENT_MIDI_SYSEX_END

11.2.5.19 const midibyte seq64::EVENT_MIDI_CLOCK

11.2.5.20 const midibyte seq64::EVENT_MIDI_SONG_F9

11.2.5.21 const midibyte seq64::EVENT_MIDI_START

11.2.5.22 const midibyte seq64::EVENT_MIDI_CONTINUE

11.2.5.23 const midibyte seq64::EVENT_MIDI_STOP

11.2.5.24 const midibyte seq64::EVENT_MIDI_SONG_FD

11.2.5.25 const midibyte seq64::EVENT_MIDI_ACTIVE_SENS

11.2.5.26 const midibyte seq64::EVENT_MIDI_RESET

11.2.5.27 const midibyte seq64::EVENT_MIDI_META

11.2.5.28 const midibyte seq64::EVENT_SYSEX

11.2.5.29 const midibyte seq64::EVENT_SYSEX_END

11.2.5.30 const midibyte seq64::EVENT_SYSEX_CONTINUE

11.2.5.31 const midibyte seq64::EVENT_NULL_CHANNEL

However, it also means that the channel is encoded in the m_status byte itself. This is our work around to be able to hold a multi-channel SMF 0 track in a sequence. In a Sequencer64 SMF 0 track, every event has a channel. In a Sequencer64 SMF 1 track, the events do not have a channel. Instead, the channel is a global value of the sequence, and is stuffed into each event when the event is played or is written to a MIDI file.

11.2.5.32 const midibyte seq64::EVENT_GET_CHAN_MASK

11.2.5.33 const midibyte seq64::EVENT_CLEAR_CHAN_MASK

11.2.5.34 const int seq64::c_midibus_output_size

These constants were also defined in midibus_portmidi.h, but we made them common to both implementations here.

The c_midibus_output_size value is passed, in mastermidibus, to snd_seq_set_output_buffer_size(). Not sure if the value needs to be so large.

11.2.5.35 const int seq64::c_midibus_input_size

Not sure if the value needs to be so large.

11.2.5.36 const int seq64::c_midibus_sysex_chunk

11.2.5.37 const midilong seq64::c_midibus

Some of the information is stored with each track (and in the midi_container-derived classes), and some is stored in the proprietary header.

Track (sequencer-specific) data:

```
            c_midibus
            c_midich
            c_timesig
            c_triggers (deprecated)
            c_triggers_new
            c_musickey (can be in footer, as well)
            c_musicscale (ditto)
            c_backsequence (ditto)
            c_transpose
```

Footer ("proprietary") data:

```
            c_midictrl
            c_midiclocks
            c_notes
            c_bpmtag (beats per minute)
            c_mutegroups

Also see the PDF file in the following project for more information about
the "proprietary" data:

    https://github.com/ahlstromcj/sequencer64-doc.git

Note that the track data is read from the MIDI file, but not written
directly to the MIDI file.  Instead, it is stored in the MIDI container as
sequences are edited to used these "sequencer-specific" features.
Also note that c_triggers has been replaced by c_triggers_new as the code
that marks the triggers stored with a sequence.

As an extension, we can also grab the key, scale, and background sequence
value selected in a sequence and write these values as track data, where
they can be read in and applied to a specific sequence, when the seqedit
object is created.  These values would not be stored in the legacy format.

Something like this could be done in the "user" configuration file, but
then the key and scale would apply to all songs.  We don't want that.

We could also add snap and note-length to the per-song defaults, but
the "user" configuration file seems like a better place to store these
preferences.
```

Track buss number.

11.2.5.38 const midilong seq64::c_midich

11.2.5.39 const midilong seq64::c_midiclocks

11.2.5.40 const midilong seq64::c_triggers

11.2.5.41 const midilong seq64::c_notes

11.2.5.42 const midilong seq64::c_timesig

11.2.5.43 const midilong seq64::c_bpmtag

11.2.5.44 const midilong seq64::c_triggers_new

11.2.5.45 const midilong seq64::c_mutegroups

11.2.5.46 const midilong seq64::c_midictrl

11.2.5.47 const midilong seq64::c_musickey

11.2.5.48 const midilong seq64::c_musicscale

11.2.5.49 const midilong seq64::c_backsequence

11.2.5.50 const int seq64::c_midi_track_ctrl

The lowest value is c_seqs_in_set ∗ 2 = 64.

I think the reason for that value is to perhaps handle two sets or something like that. Will figure it out later.

The controls are read in from the "rc" configuration files, and are written to the c_midictrl section of the "proprietary" final track in a Seq24/Sequencer64 MIDI file.

11.2.5.51 const int seq64::c_midi_control_bpm_up

11.2.5.52 const int seq64::c_midi_control_bpm_dn

11.2.5.53 const int seq64::c_midi_control_ss_up

11.2.5.54 const int seq64::c_midi_control_ss_dn

11.2.5.55 const int seq64::c_midi_control_mod_replace

11.2.5.56 const int seq64::c_midi_control_mod_snapshot

11.2.5.57 const int seq64::c_midi_control_mod_queue

11.2.5.58 const int seq64::c_midi_control_mod_gmute

11.2.5.59 const int seq64::c_midi_control_mod_glearn

11.2.5.60 const int seq64::c_midi_control_play_ss

11.2.5.61 const int seq64::c_midi_controls

11.2.5.62 const bool seq64::c_scales_policy[c_scale_size][SEQ64_OCTAVE_SIZE]

See the following sites for more information:

- http://method-behind-the-music.com/theory/scalesandkeys/
- https://en.wikipedia.org/wiki/Heptatonic_scale
- https://en.wikibooks.org/wiki/Music_Theory/Scales_and_Intervals

Note that melodic minor descends in the same way as the natural minor scale, so it descends differently than it ascends. We don't deal with that trick, at all. In the following table, the scales all start with C, but seq24/sequencer64 allow other starting notes (e.g. "keys").

```
Chromatic           C  C# D  D# E  F  F# G  G# A  A# B   Notes, chord
Major               C  .  D  .  E  F  .  G  .  A  .  B
Minor               C  .  D  Eb .  F  .  G  Ab .  Bb .
Harmonic Minor      C  .  D  Eb .  F  .  G  Ab .  .  B
Melodic Minor       C  .  D  Eb .  F  .  G  .  A  .  B   Descending diff.
C Whole Tone        C  .  D  .  E  .  F# .  G# .  A# .   C+7 chord
Blues               C  .  .  Eb .  F  Gb G  .  .  Bb .
Major Pentatonic    C  .  D  .  E  .  .  G  .  A  .  .
Minor Pentatonic    C  .  .  Eb .  F  .  G  .  .  Bb .
Octatonic 1         C  .  D  Eb .  F  Gb .  Ab A  .  B   Unimplemented
Octatonic 2         C  Db .  Eb E  F  F# G  .  A  Bb .   Unimplemented
```

11.2.5.63 const int seq64::c_scales_transpose_up[c_scale_size][SEQ64_OCTAVE_SIZE]

For example, if we simply add 1 semitone to each note, it remains a minor key, but it is in a different minor key. Using the transpositions in these arrays, the minor key remains the same minor key.

```
Major               C  .  D  .  E  F  .  G  .  A  .  B
Transpose up        2  0  2  0  1  2  0  2  0  2  0  1
Result up           D  .  E  .  F  G  .  A  .  B  .  C

Minor               C  .  D  D# .  F  .  G  G# .  A# .
Transpose up        2  0  1  2  0  2  0  1  2  0  2  0
Result up           D  .  D# F  .  G  .  G# A# .  C  .

Harmonic minor      C  .  D  Eb .  F  .  G  Ab .  .  B
Transpose up        2  .  1  2  .  2  .  1  3  .  .  1
Result up           D  .  Eb F  .  G  .  Ab B  .  .  C

Melodic minor       C  .  D  Eb .  F  .  G  .  A  .  B
Transpose up        2  .  1  2  .  2  .  2  .  2  .  1
Result up           D  .  Eb F  .  G  .  A  .  B  .  C

C Whole Tone        C  .  D  .  E  .  F# .  G# .  A# .
Transpose up        2  .  2  .  2  .  2  .  2  .  2  .
Result up           D  .  E  .  F# .  G# .  A# .  C  .

Blues               C  .  .  Eb .  F  Gb G  .  .  Bb .
Transpose up        3  .  .  2  .  1  1  3  .  .  2  .
Result up           Eb .  .  F  .  Gb G  Bb .  .  C  .

Major Pentatonic    C  .  D  .  E  .  .  G  .  A  .  .
Transpose up        2  .  2  .  3  .  .  2  .  3  .  .
Result up           D  .  E  .  G  .  .  A  .  C  .  .

Minor Pentatonic    C  .  .  Eb .  F  .  G  .  .  Bb .
Transpose up        3  .  .  2  .  2  .  3  .  .  2  .
Result up           Eb .  .  F  .  G  .  Bb .  .  C  .
```

11.2.5.64 const int seq64::c_scales_transpose_dn[c_scale_size][SEQ64_OCTAVE_SIZE]

```
Major              C  .  D  .  E  F  .  G  .  A  .  B
Transpose down     1  .  2  .  2  1  .  2  .  2  .  2
Result down        B  .  C  .  D  E  .  F  .  G  .  A


Minor              C  .  D  D# .  F  .  G  G# .  A# .
Transpose down     2  .  2  1  .  2  .  2  1  .  2  .
Result down        A# .  C  D  .  D# .  F  G  .  G# .


Harmonic minor     C  .  D  Eb .  F  .  G  Ab .  .  B
Transpose down     1  .  2  1  .  2  .  2  1  .  .  3
Result down        B  .  C  D  .  Eb .  F  G  .  .  Ab


Melodic minor      C  .  D  Eb .  F  .  G  .  A  .  B
Transpose down     1  .  2  1  .  2  .  2  .  2  .  2
Result down        B  .  C  D  .  Eb .  F  .  G  .  A


C whole tone       C  .  D  .  E  .  F# .  G# .  A# .
Transpose down     2  .  2  .  2  .  2  .  2  .  2  .
Result down        A# .  C  .  D  .  E  .  F# .  G# .


Blues              C  .  .  Eb .  F  Gb G  .  .  Bb .
Transpose down     2  .  .  3  .  2  1  1  .  .  3  .
Result down        Bb .  .  C  .  Eb F  Gb .  .  G  .


Major Pentatonic   C  .  D  .  E  .  .  G  .  A  .  .
Transpose down     3  .  2  .  2  .  .  3  .  2  .  .
Result down        A  .  C  .  D  .  .  E  .  G  .  .


Minor Pentatonic   C  .  .  Eb .  F  .  G  .  .  Bb .
Transpose down     2  .  .  3  .  2  .  2  .  .  3  .
Result down        Bb .  .  C  .  Eb .  F  .  .  G  .
```

11.2.5.65 const char seq64::c_scales_text[c_scale_size][20]

11.2.5.66 const char seq64::c_key_text[SEQ64_OCTAVE_SIZE][4]

11.2.5.67 const char seq64::c_interval_text[16][4]

11.2.5.68 const char seq64::c_chord_text[8][6]

However, we have not seen this menu in the GUI! Ah, it only appears if the user has selected a musical scale like Major or Minor.

11.2.5.69 const int seq64::c_max_instruments

With a value of 64, this is more of a sanity-check than a realistic number of instruments defined by a user.

11.2.5.70 const int seq64::c_max_busses

11.2.5.71 const std::string seq64::versiontext [static]

This value ultimately comes from the configure.ac script.

This was too redundant:

SEQ64_PACKAGE " " SEQ64_VERSION " (" SEQ64_GIT_VERSION ") " **DATE** "\n"

11.2.5.72 struct option seq64::long_options[ ] [static]

Note the terminating null structure..

11.2.5.73 const std::string seq64::s_arg_list [static]

The following string keeps track of the characters used so far. An 'x' means the character is used; an 'o' means it is used for the legacy spelling of the option.

```
0123456789 @AaBbCcDdEeFfGgHhIiJjKkLlMmNnOoPpQqRrSsTtUuVvWwXxYyZz
 ooooooooo oxxxxxx        xx xxx xxxxx x  xx xxxxx  xxx    x
```

Previous arg-list, items missing! "ChVH:lRrb:q:Lni:jJmaAM:pPusSU:x:"

11.2.5.74 const char* const seq64::s_help_1a [static]

11.2.5.75 const char* const seq64::s_help_1b [static]

11.2.5.76 const char* const seq64::s_help_2 [static]

11.2.5.77 const char* const seq64::s_help_3 [static]

11.2.5.78 const char* const seq64::s_help_4 [static]

11.2.5.79 const std::string seq64::s_build_highlight_empty [static]

11.2.5.80 const std::string seq64::s_build_lash_support [static]

11.2.5.81 const std::string seq64::s_build_jack_support [static]

11.2.5.82 const std::string seq64::s_build_jack_session [static]

11.2.5.83 const std::string seq64::s_build_pause_support [static]

11.2.5.84 const std::string seq64::s_build_use_event_map [static]

11.2.5.85 const std::string seq64::s_build_chord_generator [static]

11.2.5.86 const std::string seq64::s_build_edit_highlight [static]

11.2.5.87 const std::string seq64::s_build_timesig_tempo [static]

11.2.5.88 const std::string seq64::s_build_midi_vector [static]

11.2.5.89 const std::string seq64::s_build_solid_grid [static]

11.2.5.90 const std::string seq64::s_build_follow_progress [static]

11.2.5.91 struct charpair_t seq64::s_character_mapping[ ]

11.2.5.92 lash* seq64::s_global_lash_driver [static]

It is actually hidden in this module now, so that a function can be used in its place.

Like the font renderer, This item was once created in the main module, sequencer64.cpp. Now we make it a safer, more fool-proof, function. However, unlike the font-render, which always exists, the LASH driver is conditional, and might not be wanted. Therefore, we cannot return a reference, because there's no such thing as a null reference in C++. We have to return a pointer.

11.2.5.93 const int seq64::c_status_replace [static]

Note how they specify different bit values, as it they could be masked together to signal multiple functions.

This value signals the "replace" functionality.

11.2.5.94 const int seq64::c_status_snapshot [static]

11.2.5.95 const int seq64::c_status_queue [static]

11.2.5.96 rc_settings seq64::g_rc_settings [static]

11.2.5.97 user_settings seq64::g_user_settings [static]

11.2.5.98 const long seq64::s_handlesize [static]

11.2.5.99 const int seq64::s_jitter_amount [static]

11.2.5.100 mainwid* seq64::gs_mainwid_pointer [static]

We have decided that passing along a mainwnd reference among a number of constructors is too much and actually harder to understand and more error prone. This value is set at the end of the mainwnd constructor, but only the first time that constructor is called.

11.2.5.101 const int seq64::c_mainwid_x

Affected by the c_mainwid_border and c_mainwid_spacing values.

11.2.5.102 const int seq64::c_mainwid_y

11.2.5.103 perfedit* seq64::gs_perfedit_pointer_0 [static]

11.2.5.104 perfedit* seq64::gs_perfedit_pointer_1 [static]

11.2.5.105 const int seq64::c_select_all_notes [static]

These variables represent actions that can be applied to a selection of notes. One idea would be to add a swing-quantize action. We will reserve the value here, for notes only; not yet used or part of the action menu.

11.2.5.106 const int seq64::c_select_all_events [static]

11.2.5.107 const int seq64::c_select_inverse_notes [static]

11.2.5.108 const int seq64::c_select_inverse_events [static]

11.2.5.109 const int seq64::c_quantize_notes [static]

11.2.5.110 const int seq64::c_quantize_events [static]

11.2.5.111 const int seq64::c_tighten_events [static]

11.2.5.112 const int seq64::c_tighten_notes [static]

11.2.5.113 const int seq64::c_transpose_notes [static]

11.2.5.114 const int seq64::c_reserved [static]

11.2.5.115 const int seq64::c_transpose_h [static]

11.2.5.116 const int seq64::c_swing_notes [static]

11.2.5.117 const long seq64::s_handlesize [static]

Chapter 12

Data Structure Documentation

12.1 seq64::AbstractPerfInput Class Reference

Provides an abstract base class to provide the minimal interface for the various "perf input" classes.

Inheritance diagram for seq64::AbstractPerfInput:



Public Member Functions

- AbstractPerfInput ()

  Default constructor.
- virtual ~AbstractPerfInput ()

  Destructor, does nothing.
- virtual bool on_button_press_event (GdkEventButton *a_ev, perfroll &roll)=0
- virtual bool on_button_release_event (GdkEventButton *a_ev, perfroll &roll)=0
- virtual bool on_motion_notify_event (GdkEventMotion *a_ev, perfroll &roll)=0

Protected Attributes

- bool m_adding_pressed

  Indicates if the left mouse button is pressed while in adding mode.

12.1.1 Constructor & Destructor Documentation

12.1.1.1 seq64::AbstractPerfInput::AbstractPerfInput ( ) [inline]

12.1.1.2 virtual seq64::AbstractPerfInput::~AbstractPerfInput ( ) [inline], [virtual]

12.1.2 Member Function Documentation

12.1.2.1 virtual bool seq64::AbstractPerfInput::on_button_press_event (GdkEventButton * *a_ev*, perfroll & *roll*) [pure virtual]

Implemented in seq64::Seq24PerfInput, and seq64::FruityPerfInput.

12.1.2.2 virtual bool seq64::AbstractPerfInput::on_button_release_event (GdkEventButton * *a_ev*, perfroll & *roll*) [pure virtual]

Implemented in seq64::Seq24PerfInput, and seq64::FruityPerfInput.

12.1.2.3 virtual bool seq64::AbstractPerfInput::on_motion_notify_event (GdkEventMotion * *a_ev*, perfroll & *roll*) [pure virtual]

Implemented in seq64::Seq24PerfInput, and seq64::FruityPerfInput.

12.1.3 Field Documentation

12.1.3.1 bool seq64::AbstractPerfInput::m_adding_pressed [protected]

12.2 seq64::automutex Class Reference

Provides a mutex that locks automatically when created, and unlocks when destroyed.

Public Member Functions

- automutex (mutex &my_mutex)

  Principal constructor gets a reference to a mutex parameter, and then locks the mutex.
- ~automutex ()

  The destructor unlocks the mutex.

Private Member Functions

- automutex ()
- automutex (const automutex &)
- automutex & operator= (const automutex &)

Private Attributes

- mutex & m_safety_mutex

  Provides the mutex reference to be used for locking.

12.2.1 Detailed Description

This has a couple of benefits. First, it is threadsafe in the face of exception handling. Secondly, it can be done with just one line of code.

12.2.2 Constructor & Destructor Documentation

12.2.2.1 seq64::automutex::automutex ( ) [private]

12.2.2.2 seq64::automutex::automutex (const automutex &) [private]

12.2.2.3 seq64::automutex::automutex (mutex & *my_mutex*) [inline]

Parameters

my_mutex	The caller's mutex to be used for locking.

12.2.2.4 seq64::automutex::~automutex ( ) [inline]

12.2.3 Member Function Documentation

12.2.3.1 automutex& seq64::automutex::operator= (const automutex &) [private]

12.2.4 Field Documentation

12.2.4.1 mutex& seq64::automutex::m_safety_mutex [private]

12.3 seq64::click Class Reference

Encapsulates any possible mouse click.

Public Member Functions

- click ()

  The constructor for class click.
- click (int x, int y, int button=SEQ64_CLICK_BUTTON_LEFT, bool press=true, seq_modifier_t modkey=SEQ64_NO_MASK)

  Principal constructor for class click.
- click (const click &rhs)

  Provides a stock copy constructor.
- click & operator= (const click &rhs)

  Provides a stock principal assignment operator.
- bool is_press () const

  'Getter' function for member m_is_press
- bool is_left () const

  'Getter' function for member m_button to test for the left button.
- bool is_middle () const

  'Getter' function for member m_button to test for the middle button.
- bool is_right () const

  'Getter' function for member m_button to test for the right button.
- int x () const

  'Getter' function for member m_x
- int y () const

  'Getter' function for member m_y
- int button () const

  'Getter' function for member m_button
- seq_modifier_t modifier () const

  'Getter' function for member m_modifier
- bool mod_control () const

  'Getter' function for member m_modifier tested for Ctrl key.
- bool mod_control_shift () const

  'Getter' function for member m_modifier tested for Ctrl and Shift key.
- bool mod_super () const

  'Getter' function for member m_modifier tested for Mod4/Super/Windows key.

Private Attributes

- bool m_is_press

  Determines if the click was a press or a release event.
- int m_x

  The x-coordinate of the click.
- int m_y

  The y-coordinate of the click.
- int m_button

  The button that was pressed or released.
- seq_modifier_t m_modifier

  The optional modifier value.

12.3.1 Detailed Description

Useful in passing more generic events to non-GUI classes.

12.3.2 Constructor & Destructor Documentation

12.3.2.1 seq64::click::click ( )

Sets all members to false, zero, or the lowest good value.

12.3.2.2 seq64::click::click (int *x*, int *y*, int *button* = SEQ64_CLICK_BUTTON_LEFT, bool *press* = true, seq_modifier_t *modkey* = SEQ64_NO_MASK)

This function is the only way to set value for the click members (other than the copy constructor and principal assignment operator.

Parameters

x	The putative x value of the button click.
y	The putative y value of the button click.
button	The value of the button that was clicked, set to 1, 2, or 3.
press	Set to true if the event was a button press, false if it was a button release.
modkey	Indicates which modifier key (such as Ctrl or Alt), if any, was pressed at the same time as the click action.

12.3.2.3 seq64::click::click (const click & *rhs*)

It is nice to be explicit about these kinds of functions, even if it gets tedious.

Parameters

rhs	Provies the source object to be copied.

12.3.3 Member Function Documentation

12.3.3.1 click & seq64::click::operator= (const click & *rhs*)

It is nice to be explicit about these kinds of functions, even if it gets tedious.

Parameters

rhs	Provies the source object to be assigned from. The assignment is not made if "this" has the same address as this parameter.

Returns

Returns a reference to self for usage in a string of assignments.

12.3.3.2 bool seq64::click::is_press ( ) const [inline]

12.3.3.3 bool seq64::click::is_left ( ) const [inline]

12.3.3.4 bool seq64::click::is_middle ( ) const [inline]

12.3.3.5 bool seq64::click::is_right ( ) const [inline]

12.3.3.6 int seq64::click::x ( ) const [inline]

12.3.3.7 int seq64::click::y ( ) const [inline]

12.3.3.8 int seq64::click::button ( ) const [inline]

12.3.3.9 seq_modifier_t seq64::click::modifier ( ) const [inline]

12.3.3.10 bool seq64::click::mod_control ( ) const [inline]

12.3.3.11 bool seq64::click::mod_control_shift ( ) const [inline]

12.3.3.12 bool seq64::click::mod_super ( ) const [inline]

12.3.4 Field Documentation

12.3.4.1 bool seq64::click::m_is_press [private]

12.3.4.2 int seq64::click::m_x [private]

0 is the left-most coordinate.

12.3.4.3 int seq64::click::m_y [private]

0 is the top-most coordinate.

12.3.4.4 int seq64::click::m_button [private]

Left is 1, mmiddle is 2, and right is 3. These numbers are defined via macros, and are Linux-specific and Gtk-specific.

12.3.4.5 seq_modifier_t seq64::click::m_modifier [private]

Note that SEQ64_NO_MASK is our word for 0, meaning "no modifier".

12.4 seq64::condition_var Class Reference

A mutex works best in conjunction with a condition variable.

Inheritance diagram for seq64::condition_var:



Public Member Functions

- condition_var ()

  Initialize the condition variable with the global variable.
- void wait ()

  Waits for the condition variable.
- void signal ()

  Signals the condition variable.

Private Attributes

- pthread_cond_t m_cond

  Provides a class-specific condition variable.

Static Private Attributes

- static const pthread_cond_t sm_cond

  Provides a "global" condition variable.

Additional Inherited Members

12.4.1 Detailed Description

Therefore this class derives from the mutex class. A "has-a" relationship might be more logical than this "is-a" relationship.

12.4.2 Constructor & Destructor Documentation

12.4.2.1 seq64::condition_var::condition_var ( )

12.4.3 Member Function Documentation

12.4.3.1 void seq64::condition_var::wait ( )

12.4.3.2 void seq64::condition_var::signal ( )

12.4.4 Field Documentation

12.4.4.1 const pthread_cond_t seq64::condition_var::sm_cond [static], [private]

Define the static condition variable used by all mutex locks.

12.4.4.2 pthread_cond_t seq64::condition_var::m_cond [private]

12.5 seq64::configfile Class Reference

This class is the abstract base class for optionsfile and userfile.

Inheritance diagram for seq64::configfile:



Public Member Functions

- configfile (const std::string &name)

  Provides the string constructor for a configuration file.
- virtual ~configfile ()

  A rote destructor needed for a base class.
- virtual bool parse (perform &perf)=0
- virtual bool write (const perform &perf)=0

Protected Member Functions

- bool next_data_line (std::ifstream &file)

  Gets the next line of data from an input stream.
- void line_after (std::ifstream &file, const std::string &tag)

  This function gets a specific line of text, specified as a tag.

Protected Attributes

- std::string m_name

  Provides the name of the configuration file.
- char * m_d

  Points to an allocated buffer that holds the data for the configuration file.
- char m_line [SEQ64_LINE_MAX]

  The current line of text being processed.

12.5.1 Constructor & Destructor Documentation

12.5.1.1 seq64::configfile::configfile (const std::string & *name*)

Parameters

name	The name of the configuration file.

12.5.1.2 virtual seq64::configfile::~configfile ( ) [inline], [virtual]

12.5.2 Member Function Documentation

12.5.2.1 bool seq64::configfile::next_data_line (std::ifstream & *file*) [protected]

If the line starts with a number-sign, a space (!), or a null, it is skipped, to try the next line. This occurs until an EOF is encountered.

Member m_line is a "global" return value.

Parameters

file	Points to an input stream. We converted this item to a reference; pointers can be subject to problems. For example, what if someone passes a null pointer?

Returns

Returns true if a presumed data line was found. False is returned if not found before an EOF or a section marker ("[") is found. This is a a new (ca 2016-02-14) feature of this function, to assist in adding new data to the file.

12.5.2.2 void seq64::configfile::line_after (std::ifstream & *file*, const std::string & *tag*) [protected]

Then it gets the next non-blank line (i.e. data line) after that.

Parameters

file	Points to the input file stream.
tag	Provides a tag to be found. Lines are read until a match occurs with this tag. Normally, the tag is a section marker, such as "[user-interface]". Best to assume an exact match is needed.

12.5.2.3 virtual bool seq64::configfile::parse (perform & *perf*) [pure virtual]

Implemented in seq64::optionsfile, and seq64::userfile.

12.5.2.4 virtual bool seq64::configfile::write (const perform & *perf*) [pure virtual]

Implemented in seq64::optionsfile, and seq64::userfile.

12.5.3 Field Documentation

12.5.3.1 std::string seq64::configfile::m_name [protected]

12.5.3.2 char* seq64::configfile::m_d [protected]

12.5.3.3 char seq64::configfile::m_line[SEQ64_LINE_MAX] [protected]

This member receives an input line, and so needs to be a character buffer.

12.6 seq64::editable_event Class Reference

Provides for the management of MIDI editable events.

Inheritance diagram for seq64::editable_event:



Data Structures

- struct name_value_t

  Provides a type that contains the pair of values needed for the various lookup maps that are needed to manage editable events.

Public Types

Public Member Functions

- editable_event (const editable_events &parent)

  This constructor simply initializes all of the class members.
- editable_event (const editable_events &parent, const event &ev)

  Event constructor.
- editable_event (const editable_event &rhs)

  This copy constructor initializes most of the class members.
- editable_event & operator= (const editable_event &rhs)
- virtual ~editable_event ()

  This destructor current is a rote virtual function override.
- const editable_events & parent () const

  'Getter' function for member m_parent
- category_t category () const

  'Getter' function for member m_category
- void category (category_t c)

  'Setter' function for member m_category by value Also keeps the m_name_category member in synchrony.
- const std::string & category_string () const

  'Getter' function for member m_category
- void category (const std::string &cs)

  'Setter' function for member m_category by name Also keeps the m_name_category member in synchrony, but looks up the name, rather than using the name parameter, to avoid storing abbreviations.
- const std::string & timestamp_string () const

  'Getter' function for member m_name_timestamp
- midipulse timestamp () const

  'Getter' function for member event::get_timestamp() Implemented to allow a uniform naming convention that is not slavish to the get/set crowd [this ain't Java].
- void timestamp (midipulse ts)

  'Setter' function for member event::set_timestamp() Implemented to allow a uniform naming convention that is not slavish to the get/set crowd [this ain't Java].
- void timestamp (const std::string &ts_string)

  'Setter' function for member event::set_timestamp() [string version]
- std::string time_as_pulses ()

  Converts the current time-stamp to a string representation in units of pulses.
- std::string time_as_measures ()

  Converts the current time-stamp to a string representation in units of measures, beats, and divisions.
- std::string time_as_minutes ()

  Converts the current time-stamp to a string representation in units of hours, minutes, seconds, and fraction.
- void set_status_from_string (const std::string &ts, const std::string &s, const std::string &sd0, const std::string &sd1)

  Converts a string into an event status, along with timestamp and data bytes.
- std::string format_timestamp ()

  Formats the current timestamp member as a string.
- std::string stock_event_string ()

  Converts the event into a string desribing the full event.
- std::string status_string () const

  'Getter' function for member m_name_status
- std::string meta_string () const

  'Getter' function for member m_name_meta

- std::string seqspec_string () const

  'Getter' function for member m_name_seqspec
- std::string channel_string () const

  'Getter' function for member m_name_channel
- std::string data_string () const

  'Getter' function for member m_name_data

Static Public Member Functions

- static std::string value_to_name (midibyte value, category_t cat)

  Provides a static lookup function that returns the name, if any, associated with a midibyte value.
- static unsigned short name_to_value (const std::string &name, category_t cat)

  Provides a static lookup function that returns the value, if any, associated with a name string.

Static Public Attributes

- static const name_value_t sm_category_names [ ]

  An array of event categories and their names.
- static const name_value_t sm_channel_event_names [ ]

  An array of MIDI channel events and their names.
- static const name_value_t sm_system_event_names [ ]

  An array of MIDI system events and their names.
- static const name_value_t sm_meta_event_names [ ]

  An array of Meta events and their names.
- static const name_value_t sm_prop_event_names [ ]

  An array of Sequencer64-specific events and their names.
- static const name_value_t ∗const sm_category_arrays [ ]

  Provides for fast access (no ifs) to the correct name array for the given category.

Private Member Functions

- editable_event ()
- void analyze ()

  Analyzes an editable-event to make all the settings it needs.

Private Attributes

- const editable_events & m_parent

  Provides a reference to the container that holds this event.
- category_t m_category

  Indicates the overall category of this event, which will be category_channel_message, category_system_message, category_meta_event, and category_prop_event.
- std::string m_name_category

  Holds the name of the event category for this event.
- timestamp_format_t m_format_timestamp

  Indicates the format to display the time-stamp.
- std::string m_name_timestamp

  Holds the string version of the MIDI pulses time-stamp.

- std::string m_name_status

  Holds the name of the status value for this event.
- std::string m_name_meta

  Holds the name of the meta message, if applicable.
- std::string m_name_seqspec

  If we eventually implement the editing of the Seq24/Sequencer64 "proprietary" meta sequencer-specific events, the name of the SeqSpec will be stored here.
- std::string m_name_channel

  Holds the channel description, if applicable.
- std::string m_name_data

  Holds the data description, if applicable.

12.6.1 Detailed Description

It makes the following members of an event modifiable using human-readable strings:

```
-   m_timestamp
-   m_status
-   m_channel
-   m_data[]
```

Eventually, it would be nice to be able to edit, or at least view, the SysEx events and the Meta events. Those two will require extensions to make events out of them (SysEx is partly supported).

To the concepts of event, the editable_event class adds a category field and strings to represent all of these members.

12.6.2 Member Enumeration Documentation

12.6.2.1 enum seq64::editable_event::category_t

These tags are accompanied by category names in sm_category_names[]. The enum values are cast to midibyte values for the purposes of using the lookup infrastructure.

Enumerator

category_name Indicates that the lookup needs to be done on the category names, as listed in sm_↩ category_names[].

category_channel_message Indicates a channel event, with a value ranging from 0x80 through 0xEF. Some examples are note on/off, control change, and program change. Values are looked up in sm_↩ channel_event_names[].

category_system_message Indicates a system event, with a value ranging from 0xF0 through 0xFF. Some examples are SysEx start/end, song position, and stop/start/continue/reset. Values are looked up in sm_system_event_names[].

category_meta_event Indicates a meta event, and there is a second value that is used to look up the name of the meta event, in sm_meta_event_names[].

category_prop_event Indicates a "proprietary", Sequencer64 event. Indicates to look up the name of the event in sm_prop_event_names[]. Not sure if these kinds of events will be stored separately.

12.6.2.2 enum seq64::editable_event::timestamp_format_t

Three are supported. All editable events will share the same timestamp format, but it seems good to make this a event class member, rather than something imposed from an outside static value. We shall see.

Enumerator

timestamp_measures This format displays the time in "measures:beats:divisions" format, where measures and beats start at 1. Thus, "1:1:0" is equivalent to 0 pulses or to "0:0:0.0" in normal time values.

timestamp_time This format displays the time in "hh:mm:second.fraction" format. The value displayed should not depend upon the internal timing parameters of the event.

timestamp_pulses This format specifies a bare pulse format for the timestamp – a long integer ranging from 0 on up. Obviously, this representation depends on the PPQN value for the sequence holding this event.

12.6.3 Constructor & Destructor Documentation

12.6.3.1 seq64::editable_event::editable_event ( ) [private]

12.6.3.2 seq64::editable_event::editable_event (const editable_events & *parent*)

editable_event::editable_event () : event (), m_category (category_name), m_name_category (), m_format_↩ timestamp (timestamp_measures), m_name_timestamp (), m_name_status (), m_name_meta (), m_name_↩ seqspec (), m_name_channel (), m_name_data () { // Empty body } Principal constructor.

Parameters

parent	Provides the overall editable-events object that manages the whole set of editable-event.

12.6.3.3 seq64::editable_event::editable_event (const editable_events & *parent*, const event & *ev*)

This function basically adds all of the extra editable_event stuff to a standard event, so that the resulting editable↩ _event is container-ready.

12.6.3.4 seq64::editable_event::editable_event (const editable_event & *rhs*)

This function is currently geared only toward support of the SMF 0 channel-splitting feature. Many of the members are not set to useful values when the MIDI file is read, so we don't handle them for now.

Warning

This function does not yet copy the SysEx data. The inclusion of SysEx editable_events was not complete in Seq24, and it is still not complete in Sequencer64. Nor does it currently bother with the links.

Parameters

rhs	Provides the editable_event object to be copied.

12.6.3.5 virtual seq64::editable_event::~editable_event ( ) [inline], [virtual]

12.6.4 Member Function Documentation

12.6.4.1 std::string seq64::editable_event::value_to_name (midibyte *value,* editable_event::category_t *cat*) [static]

Parameters

value	The MIDI byte value to look up.
cat	The category of the MIDI byte. Each category calls a different name array into play.

Returns

Returns the name associated with the value. If there is no such name, then an empty string is returned.

12.6.4.2 unsigned short seq64::editable_event::name_to_value (const std::string & *name,* editable_event::category_t *cat*) [static]

The string_match() function, which can match abbreviations, case-insensitively, is used to make the string comparisons.

Parameters

name	The string value to look up.
cat	The category of the MIDI byte. Each category calls a different name array into play.

Returns

Returns the value associated with the name. If there is no such value, then SEQ64_END_OF_MIDIBYTE_↩ TABLE is returned.

12.6.4.3 editable_event & seq64::editable_event::operator= (const editable_event & *rhs*)

12.6.4.4 const editable_events& seq64::editable_event::parent ( ) const [inline]

12.6.4.5 category_t seq64::editable_event::category ( ) const [inline]

12.6.4.6 void seq64::editable_event::category (category_t *c*)

Note that a bad value is translated to the value of category_name.

Parameters

c	Provides the category value to set.

12.6.4.7 const std::string& seq64::editable_event::category_string ( ) const [inline]

12.6.4.8 void seq64::editable_event::category (const std::string & *name*)

Note that a bad value is translated to the value of category_name.

Parameters

name	Provides the category name for the category value to set.

12.6.4.9 const std::string& seq64::editable_event::timestamp_string ( ) const [inline]

12.6.4.10 midipulse seq64::editable_event::timestamp ( ) const [inline]

12.6.4.11 void seq64::editable_event::timestamp (midipulse *ts*)

Plus, we also have to set the string version at the same time.

The format of the string representation is of the format selected by the m_format_timestamp member and is set by the format_timestamp() function.

Parameters

ts	Provides the timestamp in units of MIDI pulses.

12.6.4.12 void seq64::editable_event::timestamp (const std::string & *ts_string*)

The format of the string representation is of the format selected by the m_format_timestamp member and is set by the format_timestamp() function.

Parameters

ts_string	Provides the timestamp in units of MIDI pulses.

12.6.4.13 std::string seq64::editable_event::time_as_pulses ( ) [inline]

12.6.4.14 std::string seq64::editable_event::time_as_measures ( )

Cannot be inlined because of a circular dependency between the editable_event and editable_events classes.

12.6.4.15 std::string seq64::editable_event::time_as_minutes ( )

Cannot be inlined because of a circular dependency between the editable_event and editable_events classes.

12.6.4.16 void seq64::editable_event::set_status_from_string (const std::string & *ts*, const std::string & *s*, const std::string & *sd0*, const std::string & *sd1*)

Currently, this function handles only the following two messages:

- category_channel_message
- category_system_message

After all of the numbering member items have been set, they are converted and assigned to the string versions via a call to the analyze() function.

Parameters

ts	Provides the time-stamp string of the event.
s	Provides the name of the event, such as "Program Change".
sd0	Provides the string defining the first data byte of the event.
sd1	Provides the string defining the second data byte of the event, if applicable to the event.

12.6.4.17 std::string seq64::editable_event::format_timestamp ( )

The format of the string representation is of the format selected by the m_format_timestamp member.

12.6.4.18 std::string seq64::editable_event::stock_event_string ( )

We get the time-stamp as a string, make sure the event is fully analyzed so that all items and strings are set correctly.

Returns

Returns a human-readable string describing this event.

12.6.4.19 std::string seq64::editable_event::status_string ( ) const [inline]

12.6.4.20 std::string seq64::editable_event::meta_string ( ) const [inline]

12.6.4.21 std::string seq64::editable_event::seqspec_string ( ) const [inline]

12.6.4.22 std::string seq64::editable_event::channel_string ( ) const [inline]

12.6.4.23 std::string seq64::editable_event::data_string ( ) const [inline]

12.6.4.24 void seq64::editable_event::analyze ( ) [private]

Used in the constructors. Some of the setters indirectly set the appropriate string representation, as well.

Category:

```
This function can figure out if the status byte implies a channel
message or a system message, and set the category string as well.
However, at this time, detection of Meta events (0xFF) or
Proprietary/SeqSpec events (0xFF with 0x2424) doesn't work due to lack
of context here (and due to the fact that currently such events are
not yet stored in a Sequencer64 sequence/track, and the
least-significant-byte gets masked off anyway.)
```

Status:

```
We distinguish between channel and system messages, and then one- and
two-byte messages, but don't yet distinguish the data values fully.
```

12.6.5 Field Documentation

12.6.5.1 const editable_event::name_value_t seq64::editable_event::sm_category_names [static]

Initializes the array of event/name pairs for the MIDI events categories.

Terminated by an empty string, the latter being the preferred test, for consistency with the other arrays and because 0 is often a legitimate code value.

12.6.5.2 const editable_event::name_value_t seq64::editable_event::sm_channel_event_names [static]

Initializes the array of event/name pairs for the channel MIDI events.

We split channel and system messages into two arrays, for semantic reasons and for faster linear lookups.

Terminated by an empty string.

12.6.5.3 const editable_event::name_value_t seq64::editable_event::sm_system_event_names [static]

Initializes the array of event/name pairs for the system MIDI events.

We split channel and system messages into two arrays, for semantic reasons and for faster linear lookups.

Terminated by an empty string.

12.6.5.4 const editable_event::name_value_t seq64::editable_event::sm_meta_event_names [static]

Initializes the array of event/name pairs for all of the Meta events.

Terminated only by the empty string.

12.6.5.5 const editable_event::name_value_t seq64::editable_event::sm_prop_event_names [static]

Initializes the array of event/name pairs for all of the seq24/sequencer64-specific events.

Terminated only by the empty string. Note that the numbers reflect the masking off of the high-order bits by 0x242400FF.

12.6.5.6 const editable_event::name_value_t *const seq64::editable_event::sm_category_arrays [static]

Contains pointers (references cannot be stored in an array) to the desired array for a given category.

Too bad that an array of references is not possible.

This code could be considered a bit rococo.

12.6.5.7 const editable_events& seq64::editable_event::m_parent [private]

The container's "children" need to go to their "parent" to get certain items of information.

12.6.5.8 category_t seq64::editable_event::m_category [private]

The category_name value is not set here, since that category is used only for looking up the human-readable form of the category.

12.6.5.9 std::string seq64::editable_event::m_name_category [private]

12.6.5.10 timestamp_format_t seq64::editable_event::m_format_timestamp [private]

The default is to display in timestamp_measures format.

12.6.5.11 std::string seq64::editable_event::m_name_timestamp [private]

12.6.5.12 std::string seq64::editable_event::m_name_status [private]

It will include the names of the channel messages and the system messages. The latter includes SysEx and Meta messages.

12.6.5.13 std::string seq64::editable_event::m_name_meta [private]

If not applicable, this name will be empty.

12.6.5.14 std::string seq64::editable_event::m_name_seqspec [private]

12.6.5.15 std::string seq64::editable_event::m_name_channel [private]

12.6.5.16 std::string seq64::editable_event::m_name_data [private]

12.7 seq64::editable_events Class Reference

Provides for the management of an ordered collection MIDI editable events.

Public Member Functions

- editable_events (sequence &seq, int bpm)

  This constructor hooks into the sequence object.
- editable_events (const editable_events &rhs)

  This copy constructor initializes most of the class members.
- editable_events & operator= (const editable_events &rhs)

  This principal assignment operator sets most of the class members.
- virtual ~editable_events ()

  This destructor current is a rote virtual function override.
- const midi_timing & timing () const

  'Getter' function for member m_midi_parameters
- midipulse string_to_pulses (const std::string &ts_string) const

  Calculates the MIDI pulses (divisions) from a string using one of the free functions of the calculations module.
- bool load_events ()

  Accesses the sequence's event-list, iterating through it from beginning to end, wrapping each event in the list in an editable event and inserting it into the editable-event container.
- bool save_events ()

  Erases the sequence's event container and recreates it using the edited container of editable events.
- Events & events ()

  'Getter' function for member m_events
- iterator begin ()

  'Getter' function for member m_events.begin(), non-constant version.
- const_iterator begin () const

  'Getter' function for member m_events.begin(), constant version.
- iterator end ()

  'Getter' function for member m_events.end(), non-constant version.
- const_iterator end () const

  'Getter' function for member m_events.end(), constant version.
- int count () const

  Returns the number of events stored in m_events.
- bool add (const event &e)

  Adds an event, converted to an editable_event, to the internal event list.
- bool add (const editable_event &e)

  Adds an editable event to the internal event list.
- bool replace (iterator ie, const editable_event &e)

  Provides a wrapper for the iterator form of erase(), which is the only one that the editable_events container uses.
- void remove (iterator ie)

  Provides a wrapper for the iterator form of erase(), which is the only one that sequence uses.
- void clear ()

  Provides a wrapper for clear().
- iterator current_event () const

  'Getter' function for member m_current_event The caller must make sure the iterator is not Events::end().

Private Types

- typedef event_list::event_key Key

  Types to use to with the multimap implementation.
- typedef std::pair< Key, editable_event > EventsPair
- typedef std::multimap< Key, editable_event > Events
- typedef std::multimap< Key, editable_event >::iterator iterator
- typedef std::multimap< Key, editable_event >::const_iterator const_iterator

Private Member Functions

- editable_events ()
- void current_event (iterator cei)

  'Setter' function for member m_current_event

Private Attributes

- Events m_events

  Holds the editable_events.
- iterator m_current_event

  Points to the current event, which is the event that has just been inserted.
- sequence & m_sequence

  Provides a reference to the sequence containing the events to be edited.
- midi_timing m_midi_parameters

  Holds the current settings for the sequence (and usually for the whole MIDI tune as well).

Friends

- class eventslots

12.7.1 Member Typedef Documentation

12.7.1.1 typedef event_list::event_key seq64::editable_events::Key [private]

These typenames are identical to those used in event_list, but of course they are in the editable_events scope instead. See the event_list class.

12.7.1.2 typedef std::pair<Key, editable_event> seq64::editable_events::EventsPair [private]

12.7.1.3 typedef std::multimap<Key, editable_event> seq64::editable_events::Events [private]

12.7.1.4 typedef std::multimap<Key, editable_event>::iterator seq64::editable_events::iterator [private]

12.7.1.5 typedef std::multimap<Key, editable_event>::const_iterator seq64::editable_events::const_iterator [private]

12.7.2 Constructor & Destructor Documentation

12.7.2.1 seq64::editable_events::editable_events ( ) [private]

12.7.2.2 seq64::editable_events::editable_events (sequence & *seq*, int *bpm*)

Parameters

seq	Provides a reference to the sequence object, which provides the events and some of the MIDI timing parameters.
bpm	Provides the beats/minute value, which the caller figures out how to get and provides in this parameter.

12.7.2.3 seq64::editable_events::editable_events (const editable_events & *rhs*)

Note that we need to reconstitute the event links here, as well.

Parameters

rhs	Provides the editable_events object to be copied.

12.7.2.4 virtual seq64::editable_events::~editable_events ( ) [inline], [virtual]

12.7.3 Member Function Documentation

12.7.3.1 editable_events & seq64::editable_events::operator= (const editable_events & *rhs*)

Note that we need to reconstitute the event links here, as well.

Parameters

rhs	Provides the editable_events object to be assigned.

Returns

Returns a reference to "this" object, to support the serial assignment of editable_eventss.

12.7.3.2 const midi_timing& seq64::editable_events::timing ( ) const [inline]

12.7.3.3 midipulse seq64::editable_events::string_to_pulses (const std::string & *ts_string*) const [inline]

12.7.3.4 bool seq64::editable_events::load_events ( )

Note that the new events will not have valid links (actually, no links). These links are used for associating Note Off events with their respective Note On events. To be consistent, we must take the time to reconstitute these links, using event_list::verify_and_link().

Returns

Returns true if the size of the final editable_event container matches the size of the original events container.

12.7.3.5 bool seq64::editable_events::save_events ( )

Note that the old events are replaced only if the container of editable events is not empty. There are safer ways for the user to erase all the events.

Todo Consider what to do about the sequence::m_is_modified flag.

Returns

Returns true if the size of the final event container matches the size of the original editable_events container.

12.7.3.6 Events& seq64::editable_events::events ( ) [inline]

12.7.3.7 iterator seq64::editable_events::begin ( ) [inline]

12.7.3.8 const_iterator seq64::editable_events::begin ( ) const [inline]

12.7.3.9 iterator seq64::editable_events::end ( ) [inline]

12.7.3.10 const_iterator seq64::editable_events::end ( ) const [inline]

12.7.3.11 int seq64::editable_events::count ( ) const [inline]

We like returning an integer instead of size_t, and rename the function so nobody is fooled.

12.7.3.12 bool seq64::editable_events::add (const event & *e*)

Parameters

e	Provides the regular event to be added to the list of editable events.

Returns

Returns true if the insertion succeeded, as evidenced by an increment in container size.

12.7.3.13 bool seq64::editable_events::add (const editable_event & *e*)

For the std::multimap implementation, This is an option if we want to make sure the insertion succeed.

```
std::pair<Events::iterator, bool> result = m_events.insert(p);
return result.second;
```

Parameters

e	Provides the regular event to be added to the list of editable events.

Returns

Returns true if the insertion succeeded, as evidenced by an increment in container size.

Side-effect(s) Sets m_current_event, which can be used right-away in a single-threaded context to get an iterator to the event via the current_event() accessor.

12.7.3.14 bool seq64::editable_events::replace (iterator *ie*, const editable_event & *e*) [inline]

12.7.3.15 void seq64::editable_events::remove (iterator *ie*) [inline]

12.7.3.16 void seq64::editable_events::clear ( ) [inline]

12.7.3.17 iterator seq64::editable_events::current_event ( ) const [inline]

12.7.3.18 void seq64::editable_events::current_event (iterator *cei*) [inline], [private]

Parameters

cei	Provide an iterator to the event to set as the current event.

12.7.4 Friends And Related Function Documentation

12.7.4.1 friend class eventslots [friend]

12.7.5 Field Documentation

12.7.5.1 Events seq64::editable_events::m_events [private]

12.7.5.2 iterator seq64::editable_events::m_current_event [private]

(From this event we can get the current time and other parameters.) If the container were a plain map, we could instead use a key to access it. But we can at least use an iterator, rather than a bare pointer.

12.7.5.3 sequence& seq64::editable_events::m_sequence [private]

Besides the events, this object also holds the beats/measure, beat-width, and the PPQN value. The beats/minute have to be obtained from the application's perform object, and passed to the editable_events constructor by the caller.

12.7.5.4 midi_timing seq64::editable_events::m_midi_parameters [private]

It holds the beats/minute, beats/measure, beat-width, and PPQN values needed to properly convert MIDI pulse timestamps to time and measure values.

12.8 seq64::event Class Reference

Provides events for management of MIDI events.

Inheritance diagram for seq64::event:



Public Member Functions

- event ()

  This constructor simply initializes all of the class members.
- event (const event &rhs)

  This copy constructor initializes most of the class members.
- event & operator= (const event &rhs)

  This principal assignment operator sets most of the class members.
- virtual ~event ()

  This destructor explicitly deletes m_sysex and sets it to null.
- bool operator< (const event &rhsevent) const

  If the current timestamp equal the event's timestamp, then this function returns true if the current rank is less than the event's rank.
- void set_timestamp (midipulse time)

  'Setter' function for member m_timestamp
- midipulse get_timestamp () const

  'Getter' function for member m_timestamp
- midibyte get_channel () const

  'Getter' function for member m_channel
- bool check_channel (int channel) const

  Checks the channel number to see if the event's channel matches it, or if the event has no channel.
- void mod_timestamp (midipulse a_mod)

  Calculates the value of the current timestamp modulo the given parameter.
- void set_status (midibyte status)

  Sets the m_status member to the value of status.
- void set_status (midibyte eventcode, midibyte channel)

  This overload is useful when synthesizing events, such as converting a Note On event with a velocity of zero to a Note Off event.
- void set_channel (midibyte channel)

  Sets the channel "nybble", without modifying the status "nybble".
- midibyte get_status () const

  'Getter' function for member m_status
- void set_data (midibyte d1)

  Clears the most-significant-bit of the d1 parameter, and sets it into the first byte of m_data.
- void set_data (midibyte d1, midibyte d2)

  Clears the most-significant-bit of both parameters, and sets them into the first and second bytes of m_data.
- void get_data (midibyte &d0, midibyte &d1) const

  Retrieves the two data bytes from m_data[] and copies each into its respective parameter.
- void increment_data1 ()

  Increments the first data byte (m_data[0]) and clears the most significant bit.
- void decrement_data1 ()

  Decrements the first data byte (m_data[0]) and clears the most significant bit.
- void increment_data2 ()

  Increments the second data byte (m_data[1]) and clears the most significant bit.
- void decrement_data2 ()

  Decrements the second data byte (m_data[1]) and clears the most significant bit.
- void restart_sysex ()

  Deletes and clears out the SYSEX buffer.
- bool append_sysex (midibyte *data, int len)

  Appends SYSEX data to a new buffer.
- midibyte * get_sysex () const

'Getter' function for member m_sysex

- void set_sysex_size (int len)

  'Setter' function for member m_sysex_size
- int get_sysex_size () const

  'Getter' function for member m_sysex_size
- void link (event *ev)

  Sets m_has_link and sets m_link to the provided event pointer.
- event * get_linked () const

  'Getter' function for member m_linked
- bool is_linked () const

  'Getter' function for member m_has_link
- void clear_link ()

  'Setter' function for member m_has_link
- void paint ()

  'Setter' function for member m_painted
- void unpaint ()

  'Setter' function for member m_painted
- bool is_painted () const

  'Getter' function for member m_painted
- void mark ()

  'Setter' function for member m_marked
- void unmark ()

  'Setter' function for member m_marked
- bool is_marked () const

  'Getter' function for member m_marked
- void select ()

  'Setter' function for member m_selected
- void unselect ()

  'Setter' function for member m_selected
- bool is_selected () const

  'Getter' function for member m_selected
- void make_clock ()

  Sets m_status to EVENT_MIDI_CLOCK;.
- midibyte data (int index) const

  'Getter' function for member m_data[]
- midibyte get_note () const

  Assuming m_data[] holds a note, get the note number, which is in the first data byte, m_data[0].
- void set_note (midibyte note)

  Sets the note number, clearing off the most-significant-bit and assigning it to the first data byte, m_data[0].
- midibyte get_note_velocity () const

  'Getter' function for member m_data[1], the note velocity.
- void set_note_velocity (int a_vel)

  Sets the note velocity, which is held in the second data byte, and clearing off the most-significant-bit, storing it in m_data[1].
- bool is_note_on () const
- bool is_note_off () const
- bool is_note () const

  Returns true if m_status is a Note On, Note Off, or Aftertouch message.
- void print () const

  Prints out the timestamp, data size, the current status byte, any SYSEX data if present, or the two data bytes for the status byte.
- int get_rank () const

  This function is used in sorting MIDI status events (e.g.

Static Public Member Functions

- static bool is_channel_msg (midibyte m)

  Static test for the channel message/statuse values: Note On, Note Off, Aftertouch, Control Change, Program Change, Channel Pressure, and Pitch Wheel.
- static bool is_one_byte_msg (midibyte m)

  Static test for channel messages that have only one data byte: Program Change and Channel Pressure.
- static bool is_two_byte_msg (midibyte m)

  Static test for channel messages that have two data bytes: Note On, Note Off, Control Change, Aftertouch, and Pitch Wheel.
- static bool is_note_msg (midibyte m)

  Static test for messages that involve notes and velocity: Note On, Note Off, and Aftertouch.
- static bool is_desired_cc_or_not_cc (midibyte m, midibyte cc, midibyte datum)

  Static test for channel messages that are either not control-change messages, or are and match the given controller value.

Private Attributes

- midipulse m_timestamp

  Provides the MIDI timestamp in ticks, otherwise known as the "pulses" in "pulses per quarter note" (PPQN).
- midibyte m_status

  This is the status byte without the channel.
- midibyte m_channel

  In order to be able to handle MIDI channel-splitting of an SMF 0 file, we need to store the channel, even if we override it when playing the MIDI data.
- midibyte m_data [SEQ64_MIDI_DATA_BYTE_COUNT]

  The two bytes of data for the MIDI event.
- midibyte * m_sysex

  Points to the data buffer for SYSEX messages.
- int m_sysex_size

  Gives the size of the SYSEX message.
- event * m_linked

  This event is used to link Note Ons and Offs together.
- bool m_has_link

  Indicates that a link has been made.
- bool m_selected

  Answers the question "is this event selected in editing.".
- bool m_marked

  Answers the question "is this event marked in processing.".
- bool m_painted

  Answers the question "is this event being painted.".

12.8.1 Detailed Description

A MIDI event consists of 3 bytes:

```
-#  Status byte, 1sssnnn, where the sss bits specify the type of
    message, and the nnnn bits denote the channel number.
    The status byte always starts with 0.
-#  The first data byte, 0xxxxxxx, where the data byte always
    start with 0, and the xxxxxxx values range from 0 to 127.
-#  The second data byte, 0xxxxxxx.
```

This class may have too many member functions.

12.8.2 Constructor & Destructor Documentation

12.8.2.1 seq64::event::event ( )

12.8.2.2 seq64::event::event (const event & *rhs*)

This function is currently geared only toward support of the SMF 0 channel-splitting feature. Many of the members are not set to useful values when the MIDI file is read, so we don't handle them for now.

Note that now events are also copied when creating the editable_events container, so this function is even more important. The event links, for linking Note Off events to their respective Note On events, are dropped. Generally, they will need to be reconstituted by calling the event_list::verify_and_link() function.

Warning

This function does not yet copy the SysEx data. The inclusion of SysEx events was not complete in Seq24, and it is still not complete in Sequencer64. Nor does it currently bother with the links, as noted above.

Parameters

rhs	Provides the event object to be copied.

12.8.2.3 seq64::event::~event ( ) [virtual]

The restart_sysex() function does what we need.

12.8.3 Member Function Documentation

12.8.3.1 event & seq64::event::operator= (const event & *rhs*)

This function is currently geared only toward support of the SMF 0 channel-splitting feature. Many of the member are not set to useful value when the MIDI file is read, so we don't handle them for now.

Warning

This function does not yet copy the SysEx data. The inclusion of SysEx events was not complete in Seq24, and it is still not complete in Sequencer64. Nor does it currently bother with the links.

Parameters

rhs	Provides the event object to be assigned.

Returns

Returns a reference to "this" object, to support the serial assignment of events.

12.8.3.2 bool seq64::event::operator< (const event & *rhs*) const

Otherwise, it returns true if the current timestamp is less than the event's timestamp.

Warning

The less-than operator is supposed to support a "strict weak ordering", and is supposed to leave equivalent values in the same order they were before the sort. However, every time we load and save our sample MIDI file, events get reversed. Here are program-changes that get reversed:

```
    Save N:     0070: 6E 00 C4 48 00 C4 0C 00  C4 57 00 C4 19 00 C4 26
    Save N+1:   0070: 6E 00 C4 26 00 C4 19 00  C4 57 00 C4 0C 00 C4 48


The 0070 is the offset within the versions of the
b4uacuse-seq24.midi file.

Because of this mis-feature, and the very slow speed of loading a MIDI
file when Sequencer64 is built for debugging, we are exploring using
an std::mulitmap instead of an std::list.  Search for occurrences of
the SEQ64_USE_EVENT_MAP macro. (This actually works better than a
list, for loading MIDI event, we have found, but may cause the upper
limit of the number of playing sequences to drop a little, due to the
overhead of incrementing multimap iterators versus list iterators).
```

Parameters

rhs	The object to be compared against.

Returns

Returns true if the time-stamp and "rank" are less than those of the comparison object.

12.8.3.3 void seq64::event::set_timestamp (midipulse *time*) [inline]

Parameters

time	Provides the time value, in ticks, to set as the timestamp.

12.8.3.4 midipulse seq64::event::get_timestamp ( ) const [inline]

12.8.3.5 midibyte seq64::event::get_channel ( ) const [inline]

12.8.3.6 bool seq64::event::check_channel (int *channel*) const [inline]

Used in the SMF 0 track-splitting code.

Parameters

channel	The channel to check.

Returns

Returns true if the given channel matches the event's channel.

12.8.3.7 static bool seq64::event::is_channel_msg (midibyte *m*) [inline], [static]

This function requires that the channel data have already been masked off.

Parameters

m	The channel status or message byte to be tested, with the channel bits masked off.

Returns

Returns true if the byte represents a MIDI channel message.

12.8.3.8 static bool seq64::event::is_one_byte_msg (midibyte *m*) [inline], [static]

The rest of the channel messages have two data bytes. This function requires that the channel data have already been masked off.

Parameters

m	The channel status or message byte to be tested, with the channel bits masked off.

Returns

Returns true if the byte represents a MIDI channel message that has only one data byte. However, if this function returns false, it might not be a channel message at all, so be careful.

12.8.3.9 static bool seq64::event::is_two_byte_msg (midibyte *m*) [inline], [static]

This function requires that the channel data have already been masked off.

Parameters

m	The channel status or message byte to be tested, with the channel bits masked off.

Returns

Returns true if the byte represents a MIDI channel message that has two data bytes. However, if this function returns false, it might not be a channel message at all, so be careful.

12.8.3.10 static bool seq64::event::is_note_msg (midibyte *m*) [inline], [static]

This function requires that the channel data have already been masked off.

Parameters

m	The channel status or message byte to be tested, with the channel bits masked off.

Returns

Returns true if the byte represents a MIDI note message.

12.8.3.11 static bool seq64::event::is_desired_cc_or_not_cc (midibyte *m,* midibyte *cc,* midibyte *datum*) [inline], [static]

Note

The old logic was the first line, but can be simplified to the second line; the third line shows the abstract representation. Also made sure of this using a couple truth tables.

```
(m != EVENT_CONTROL_CHANGE) || (m == EVENT_CONTROL_CHANGE && d == cc)
(m != EVENT_CONTROL_CHANGE) || (d == cc)
a || (! a && b)  =>  a || b
```

```
\param m
     The channel status or message byte to be tested, with the channel
     bits masked off.

\param cc
     The desired cc value, which the datum must match, if the message is
     a control-change message.

\param datum
     The current datum, to be compared to cc, if the message is a
     control-change message.

\return
     Returns true if the message is not a control-change, or if it is
     and the cc and datum parameters match.
```

12.8.3.12 void seq64::event::mod_timestamp (midipulse *a_mod*) [inline]

Parameters

a_mod	The tick value to mod the timestamp against.

Returns

Returns a value ranging from 0 to a_mod-1.

12.8.3.13 void seq64::event::set_status (midibyte *status*)

If a_status is a channel event, then the channel portion of the status is cleared using a bitwise AND against EVE↩ NT_CLEAR_CHAN_MASK.

Found in yet another fork of seq24:

```
// ORL fait de la merde
```

He also provided a very similar routine: set_status_midibus().

Parameters

status	The status byte, perhaps read from a MIDI file or edited in the sequencer's event editor. Sometime, this byte will have the channel nybble masked off. If that is the case, the eventcode/channel overload of this function is more appropriate.

12.8.3.14 void seq64::event::set_status (midibyte *eventcode,* midibyte *channel*)

Parameters

eventcode	The status byte, perhaps read from a MIDI file. This byte is assumed to have already had its low nybble cleared by masking against EVENT_CLEAR_CHAN_MASK.
channel	The channel byte. Combined with the event-code, this makes a valid MIDI "status" byte. This byte is assume to have already had its high nybble cleared by masking against EVENT_GET_CHAN_MASK.

12.8.3.15 void seq64::event::set_channel (midibyte *channel*) [inline]

It actually just sets the m_channel member. Note that the sequence channel generally overrides this value in the usage of the event.

Parameters

channel	The channel byte to be set.

12.8.3.16 midibyte seq64::event::get_status ( ) const [inline]

12.8.3.17 void seq64::event::set_data (midibyte *d1*) [inline]

The second byte of data is zeroed. The data bytes are in a two =-byte array member, m_data.

Parameters

d1	The byte value to set as the first data byte.

12.8.3.18 void seq64::event::set_data (midibyte *d1,* midibyte *d2*) [inline]

Parameters

d1	The first byte value to set.
d2	The second byte value to set.

12.8.3.19 void seq64::event::get_data (midibyte & *d0,* midibyte & *d1*) const [inline]

Parameters

d0	[out] The return reference for the first byte.
d1	[out] The return reference for the first byte.

12.8.3.20 void seq64::event::increment_data1 ( ) [inline]

12.8.3.21 void seq64::event::decrement_data1 ( ) [inline]

12.8.3.22 void seq64::event::increment_data2 ( ) [inline]

12.8.3.23 void seq64::event::decrement_data2 ( ) [inline]

12.8.3.24 void seq64::event::restart_sysex ( )

12.8.3.25 bool seq64::event::append_sysex (midibyte * *data,* int *dsize*)

First, a buffer of size m_sysex_size+dsize is created. The existing SYSEX data (stored in m_sysex) is copied to this buffer. Then the data represented by data and dsize is appended to that data buffer. Then the original SYSEX buffer, m_sysex, is deleted, and m_sysex is assigned to the new buffer.

Parameters

data	Provides the additional SYSEX data. If not provided, nothing is done, and false is returned.
dsize	Provides the size of the additional SYSEX data. If not provided, nothing is done.

Returns

Returns false if there was an EVENT_SYSEX_END byte in the appended data, or if an error occurred, and the caller needs to stop trying to process the data.

12.8.3.26 midibyte* seq64::event::get_sysex ( ) const [inline]

12.8.3.27 void seq64::event::set_sysex_size (int *len*) [inline]

Parameters

len	Provides the length value to set as the size of the SYSEX data.

12.8.3.28 int seq64::event::get_sysex_size ( ) const [inline]

12.8.3.29 void seq64::event::link (event * *ev*) [inline]

Parameters

a_event	Provides a pointer to the event value to set. If null, then m_has_link is set to false, to guarantee that is_linked() is correct.

12.8.3.30 event* seq64::event::get_linked ( ) const [inline]

12.8.3.31 bool seq64::event::is_linked ( ) const [inline]

12.8.3.32 void seq64::event::clear_link ( ) [inline]

12.8.3.33 void seq64::event::paint ( ) [inline]

12.8.3.34 void seq64::event::unpaint ( ) [inline]

12.8.3.35 bool seq64::event::is_painted ( ) const [inline]

12.8.3.36 void seq64::event::mark ( ) [inline]

12.8.3.37 void seq64::event::unmark ( ) [inline]

12.8.3.38 bool seq64::event::is_marked ( ) const [inline]

12.8.3.39 void seq64::event::select ( ) [inline]

12.8.3.40 void seq64::event::unselect ( ) [inline]

12.8.3.41 bool seq64::event::is_selected ( ) const [inline]

12.8.3.42 void seq64::event::make_clock ( ) [inline]

12.8.3.43 midibyte seq64::event::data (int *index*) const [inline]

12.8.3.44 midibyte seq64::event::get_note ( ) const [inline]

12.8.3.45 void seq64::event::set_note (midibyte *note*) [inline]

Parameters

note	Provides the note value to set.

12.8.3.46 midibyte seq64::event::get_note_velocity ( ) const [inline]

12.8.3.47 void seq64::event::set_note_velocity (int *a_vel*) [inline]

Parameters

a_vel	Provides the velocity value to set.

12.8.3.48 bool seq64::event::is_note_on ( ) const [inline]

Returns

Returns true if m_status is EVENT_NOTE_ON.

12.8.3.49 bool seq64::event::is_note_off ( ) const [inline]

Returns

Returns true if m_status is EVENT_NOTE_OFF.

12.8.3.50 bool seq64::event::is_note ( ) const [inline]

All of these are notes, associated with a MIDI key value. Uses the static function is_note_msg().

Returns

The return value of is_note_msg() is returned.

12.8.3.51 void seq64::event::print ( ) const

12.8.3.52 int seq64::event::get_rank ( ) const

The ranking, from high to low, is note off, note on, aftertouch, channel pressure, and pitch wheel, control change, and program changes.

note on/off, aftertouch, control change, etc.) The sort order is not determined by the actual status values.

The lower the ranking the more upfront an item comes in the sort order.

Returns

Returns the rank of the current m_status byte.

12.8.4 Field Documentation

12.8.4.1 midipulse seq64::event::m_timestamp [private]

12.8.4.2 midibyte seq64::event::m_status [private]

The channel will be appended on the MIDI bus. The high nibble = type of event; The low nibble = channel. Bit 7 is present in all status bytes.

12.8.4.3 midibyte seq64::event::m_channel [private]

This member adds another 4 bytes to the event object, most likely.

12.8.4.4 midibyte seq64::event::m_data[SEQ64_MIDI_DATA_BYTE_COUNT] [private]

Remember that the most-significant bit of a data byte is always 0.

12.8.4.5 midibyte* seq64::event::m_sysex [private]

This really ought to be a Boost or STD scoped pointer. Currently, it doesn't seem to be used.

12.8.4.6 int seq64::event::m_sysex_size [private]

12.8.4.7 event* seq64::event::m_linked [private]

12.8.4.8 bool seq64::event::m_has_link [private]

This item is used [via the get_link() and link() accessors] in the sequence class.

12.8.4.9 bool seq64::event::m_selected [private]

12.8.4.10 bool seq64::event::m_marked [private]

12.8.4.11 bool seq64::event::m_painted [private]

12.9 seq64::event_list::event_key Class Reference

Provides a key value for an event map.

Public Member Functions

- event_key (midipulse tstamp, int rank)

  Principal event_key constructor.
- event_key (const event &e)

  Event-based constructor.
- bool operator< (const event_key &rhs) const

  Provides the minimal operator needed to sort events using an event_key.

Private Attributes

- midipulse m_timestamp

  The primary key-value for the key.
- int m_rank

  The sub-key-value for the key.

12.9.1 Detailed Description

Its types match the m_timestamp and get_rank() function of this event class.

12.9.2 Constructor & Destructor Documentation

12.9.2.1 seq64::event_list::event_key::event_key (midipulse *tstamp,* int *rank*)

Parameters

tstamp	The time-stamp is the primary part of the key. It is the most important key item.
rank	Rank is an arbitrary number used to prioritize events that have the same time-stamp. See the event::get_rank() function for more information.

12.9.2.2 seq64::event_list::event_key::event_key (const event & *rhs*)

This constructor makes it even easier to create an event_key. Note that the call to event::get_rank() makes a simple calculation based on the status of the event.

Parameters

rhs	Provides the event key to be copied.

12.9.3 Member Function Documentation

12.9.3.1 bool seq64::event_list::event_key::operator< (const event_key & *rhs*) const

Parameters

rhs	Provides the event key to be compared against.

Returns

Returns true if the rank and timestamp of the current object are less than those of rhs.

12.9.4 Field Documentation

12.9.4.1 midipulse seq64::event_list::event_key::m_timestamp [private]

12.9.4.2 int seq64::event_list::event_key::m_rank [private]

12.10 seq64::event_list Class Reference

The event_list class is a receptable for MIDI events.

Data Structures

- class event_key

  Provides a key value for an event map.

Public Member Functions

- event_list ()

  Principal constructor.
- event_list (const event_list &a_rhs)

  Copy constructor.
- event_list & operator= (const event_list &a_rhs)

  Principal assignment operator.
- ~event_list ()

  A rote destructor.
- iterator begin ()

  'Getter' function for member m_events.begin(), non-constant version.
- const_iterator begin () const

  'Getter' function for member m_events.begin(), constant version.
- iterator end ()

  'Getter' function for member m_events.end(), non-constant version.
- const_iterator end () const

  'Getter' function for member m_events.end(), constant version.
- int count () const

  Returns the number of events stored in m_events.
- bool empty () const

  Returns true if there are no events.
- bool add (const event &e, bool postsort=true)

  Adds an event to the internal event list in an optionally sorted manner.
- bool is_modified () const

  'Getter' function for member m_is_modified
- void unmodify ()

  'Setter' function for member m_is_modified This function may be needed by some of the sequence editors.
- void remove (iterator ie)

  Provides a wrapper for the iterator form of erase(), which is the only one that sequence uses.
- void clear ()

  Provides a wrapper for clear().
- void merge (event_list &el, bool presort=true)

  Provides a merge operation for the event multimap analogous to the merge operation for the event list.
- void sort ()

  Wrapper for std::list::sort(), or, since multimaps are always sorted, an empty function.

Static Public Member Functions

- static event & dref (iterator ie)

  Dereference access for list or map.
- static const event & dref (const_iterator ie)

  Dereference const access for list or map.

Private Types

- typedef std::multimap< event_key, event > Events

  Types to use to swap between list and multimap implementations.
- typedef std::pair< event_key, event > EventsPair
- typedef std::multimap< event_key, event >::iterator iterator
- typedef std::multimap< event_key, event >::const_iterator const_iterator

Private Member Functions

- void link_new ()

  Links a new event.
- void clear_links ()

  Clears all event links and unmarks them all.
- void verify_and_link (midipulse slength)

  This function verifies state: all note-ons have an off, and it links note-offs with their note-ons.
- void mark_selected ()

  Marks all selected events.
- void mark_out_of_range (midipulse slength)

  Marks all events that have a time-stamp that is out of range.
- void mark_all ()

  Marks all events.
- void unmark_all ()

  Unmarks all events.
- bool remove_marked ()

  Removes marked events.
- void unpaint_all ()

  Unpaints all list-events.
- int count_selected_notes () const

  Counts the selected note-on events in the event list.
- bool any_selected_notes () const

  Indicates that at least one note is selected.
- int count_selected_events (midibyte status, midibyte cc) const

  Counts the selected events, with the given status, in the event list.
- void select_all ()

  Selects all events, unconditionally.
- void unselect_all ()

  Deselects all events, unconditionally.
- void print () const

  Prints a list of the currently-held events.
- const Events & events () const

  'Getter' function for member m_events

Private Attributes

- Events m_events

  This list holds the current pattern/sequence events.
- bool m_is_modified

  A new flag to indicate if an event was added or removed.

Friends

- class editable_events
- class midi_container
- class midi_splitter
- class sequence

12.10.1 Detailed Description

Two implementations, an std::multimap, and the original, an std::list, are provided for comparison, and are selected at build time, by manually defining the SEQ64_USE_EVENT_MAP macro near the top of this module.

12.10.2 Member Typedef Documentation

12.10.2.1 typedef std::multimap<event_key, event> seq64::event_list::Events [private]

12.10.2.2 typedef std::pair<event_key, event> seq64::event_list::EventsPair [private]

12.10.2.3 typedef std::multimap<event_key, event>::iterator seq64::event_list::iterator [private]

12.10.2.4 typedef std::multimap<event_key, event>::const_iterator seq64::event_list::const_iterator [private]

12.10.3 Constructor & Destructor Documentation

12.10.3.1 seq64::event_list::event_list ( )

12.10.3.2 seq64::event_list::event_list (const event_list & *rhs*)

Parameters

rhs	Provides the event list to be copied.

12.10.3.3 seq64::event_list::~event_list ( )

12.10.4 Member Function Documentation

12.10.4.1 event_list & seq64::event_list::operator= (const event_list & *rhs*)

Follows the stock rules for such an operator, just assigning member values.

Parameters

rhs	Provides the event list to be assigned.

12.10.4.2 iterator seq64::event_list::begin ( ) [inline]

12.10.4.3 const_iterator seq64::event_list::begin ( ) const [inline]

12.10.4.4 iterator seq64::event_list::end ( ) [inline]

12.10.4.5 const_iterator seq64::event_list::end ( ) const [inline]

12.10.4.6 int seq64::event_list::count ( ) const [inline]

We like returning an integer instead of size_t, and rename the function so nobody is fooled.

12.10.4.7 bool seq64::event_list::empty ( ) const [inline]

12.10.4.8 bool seq64::event_list::add (const event & *e*, bool *postsort* = true)

It is a wrapper, wrapper for insert() or push_front(), with an option to call sort().

For the std::multimap implementation, This is an option if we want to make sure the insertion succeed.

```
std::pair<Events::iterator, bool> result = m_events.insert(p);
return result.second;
```

Warning

This pushing (and, in writing the MIDI file, the popping), causes events with identical timestamps to be written in reverse order. Doesn't affect functionality, but it's puzzling until one understands what is happening. That's why we're now preferring to use a multimap as the container.

Parameters

e	Provides the event to be added to the list.
postsort	If true, and the std::list implementation has been built in, then the event list is sorted after the addition. This is a time-consuming operation.

Returns

Returns true if the insertion succeeded, as evidenced by an increment in container size.

12.10.4.9 bool seq64::event_list::is_modified ( ) const [inline]

12.10.4.10 void seq64::event_list::unmodify ( ) [inline]

But use it with great caution.

12.10.4.11 void seq64::event_list::remove (iterator *ie*) [inline]

Currently, no check on removal is performed. Set the modified-flag.

Parameters

ie	Provides the iterator to the event to be removed.

12.10.4.12 void seq64::event_list::clear ( ) [inline]

Set the modified-flag.

12.10.4.13 void seq64::event_list::merge (event_list & *el*, bool *presort* = true)

We have certain constraints to preserve, as the following discussion shows.

For std::list, sequence merges list T into list A by first calling T.sort(), and then A.merge(T). The merge() operation merges T into A by transferring all of its elements, at their respective ordered positions, into A. Both containers must already be ordered.

The merge effectively removes all the elements in T (which becomes empty), and inserts them into their ordered position within container (which expands in size by the number of elements transferred). The operation is performed without constructing nor destroying any element, whether T is an lvalue or an rvalue, or whether the value-type supports move-construction or not.

Each element of T is inserted at the position that corresponds to its value according to the strict weak ordering defined by operator $<$. The resulting order of equivalent elements is stable (i.e. equivalent elements preserve the relative order they had before the call, and existing elements precede those equivalent inserted from x). The function does nothing if (&x == this).

For std::multimap, sorting is automatic. However, unless move-construction is supported, merging will be less efficient than for the list version. Also, we need a way to include duplicates of each event, so we need to use a multimap. Once all this setup, merging is really just insertion. And, since sorting isn't needed, the multimap actually turns out to be faster.

Parameters

el	Provides the event list to be merged into the current event list.
presort	If true, the events are presorted. This is a requirement for merging an std::list, but is a no-op for the std::multimap implementation.

12.10.4.14 void seq64::event_list::sort ( ) [inline]

12.10.4.15 static event& seq64::event_list::dref (iterator *ie*) [inline], [static]

Parameters

ie	Provides the iterator to the event to which to get a reference.

12.10.4.16 static const event& seq64::event_list::dref (const_iterator *ie*) [inline], [static]

Parameters

ie	Provides the iterator to the event to which to get a reference.

12.10.4.17 void seq64::event_list::link_new ( ) [private]

This function checks for a note on, then look for its note off. This function is provided in the event_list because it does not depend on any external data. Also note that any desired thread-safety must be provided by the caller.

12.10.4.18 void seq64::event_list::clear_links ( ) [private]

12.10.4.19 void seq64::event_list::verify_and_link (midipulse *slength*) [private]

Not threadsafe

Parameters

slength	Provides the length beyond which events will be pruned.

12.10.4.20 void seq64::event_list::mark_selected ( ) [private]

12.10.4.21 void seq64::event_list::mark_out_of_range (midipulse *slength*) [private]

Used for killing (pruning) those events not in range. If the current time-stamp is greater than the length, then the event is marked for pruning.

Note

This code was comparing the timestamp as greater than or equal to the sequence length. However, being equal is fine. This may explain why the midifile code would add one tick to the length of the last note when processing the end-of-track.

Parameters

slength	Provides the length beyond which events will be pruned.

12.10.4.22 void seq64::event_list::mark_all ( ) [private]

Not yet used, but might come in handy with the event editor dialog.

12.10.4.23 void seq64::event_list::unmark_all ( ) [private]

12.10.4.24 bool seq64::event_list::remove_marked ( ) [private]

Note how this function handles removing a value to avoid incrementing a now-invalid iterator.

Threadsafe

Returns

Returns true if at least one event was removed.

12.10.4.25 void seq64::event_list::unpaint_all ( ) [private]

12.10.4.26 int seq64::event_list::count_selected_notes ( ) const [private]

12.10.4.27 bool seq64::event_list::any_selected_notes ( ) const [private]

Acts like event_list::count_selected_notes(), but stops after finding a selected note. We could add a flag to count↩_selected_notes() to break, I suppose.

Returns

Returns true if at least one note is selected.

12.10.4.28 int seq64::event_list::count_selected_events (midibyte *status*, midibyte *cc*) const [private]

If the event is a control change (CC), then it must also match the given CC value.

Parameters

status	The desired status value to count.
cc	The desired control-change to count. Used only if the status parameter indicates a control-change event.

Returns

Returns the number of selected events.

12.10.4.29 void seq64::event_list::select_all ( ) [private]

12.10.4.30 void seq64::event_list::unselect_all ( ) [private]

12.10.4.31 void seq64::event_list::print ( ) const [private]

12.10.4.32 const Events& seq64::event_list::events ( ) const [inline], [private]

12.10.5 Friends And Related Function Documentation

12.10.5.1 friend class editable_events [friend]

12.10.5.2 friend class midi_container [friend]

12.10.5.3 friend class midi_splitter [friend]

12.10.5.4 friend class sequence [friend]

12.10.6 Field Documentation

12.10.6.1 Events seq64::event_list::m_events [private]

12.10.6.2 bool seq64::event_list::m_is_modified [private]

We may need to give client code a way to reload the sequence. This is currently an issue when a seqroll and an eventedit/eventslots are active for the same sequence.

12.11 seq64::eventedit Class Reference

This class supports an Event Editor that is used to tweak the details of events and get a better idea of the mix of events in a sequence.

Inheritance diagram for seq64::eventedit:



Public Member Functions

- eventedit (perform &p, sequence &seq)

Principal constructor, has a reference to a perform object.

- virtual ~eventedit ()

  This rote constructor does nothing.

Private Member Functions

- void enqueue_draw ()

  Helper wrapper for calling eventslots::queue_draw().
- void set_seq_title (const std::string &title)

  Sets m_label_seq_name to the title.
- void set_seq_time_sig (const std::string &sig)

  Sets m_label_time_sig to the time-signature string.
- void set_seq_ppqn (const std::string &p)

  Sets m_label_ppqn to the parts-per-quarter-note string.
- void set_seq_count ()

  Sets m_label_ev_count to the number-of-events string.
- void set_event_category (const std::string &c)

  Sets m_label_category to the category string.
- void set_event_timestamp (const std::string &ts)

  Sets m_entry_ev_timestamp to the time-stamp string.
- void set_event_name (const std::string &n)

  Sets m_entry_ev_name to the name-of-event string.
- void set_event_data_0 (const std::string &d)

  Sets m_entry_ev_data_0 to the first data byte string.
- void set_event_data_1 (const std::string &d)

  Sets m_entry_data_1 to the second data byte string.
- void perf_modify ()

  Provides a way to mark the perform object as modified, when the modified sequence is saved.
- void set_dirty (bool flag=true)

  Sets the "modified" status of the user-interface.
- void v_adjustment (int value)

  Sets the parameters for the vertical scroll-bar, using only the value parameter.
- void v_adjustment (int value, int lower, int upper)

  Sets the parameters for the vertical scroll-bar that is associated with the eventslots event-list user-interface.
- void change_focus (bool set_it=true)

  Changes what perform and mainwid see as the "current sequence".
- void close_out ()

  Handles closing the sequence editor, common code for handle_cancel() and handle_close().
- void handle_close ()

  Handles closing the sequence editor.
- void handle_delete ()

  Initiates the deletion of the current editable event.
- void handle_insert ()

  Initiates the insertion of a new editable event.
- void handle_modify ()

  Passes the edited fields to the current editable event in the eventslot.
- void handle_save ()

  Handles saving the edited data back to the original sequence.
- void handle_cancel ()

  Cancels the edits and closes the dialog box.

- void on_realize ()

  This callback function calls the base-class on_realize() function.
- void on_set_focus (Widget *focus)

  On receiving focus, attempt to tell mainwid that this sequence is now the current sequence.
- bool on_focus_in_event (GdkEventFocus *)

  Implements the on-focus event handling.
- bool on_focus_out_event (GdkEventFocus *)

  Implements the on-unfocus event handling.
- bool on_key_press_event (GdkEventKey *ev)

  This function is the callback for a key-press event.
- bool on_delete_event (GdkEventAny *event)

  Handles an on-delete event.

Private Attributes

- Gtk::Table * m_table

  A whole horde of GUI elements.
- Gtk::Adjustment * m_vadjust

  Vertical paging for event list.
- Gtk::VScrollbar * m_vscroll

  Vertical scroll for event list.
- eventslots * m_eventslots

  Drawing area for events.
- Gtk::HBox * m_htopbox

  Padding at the top of the dialog.
- Gtk::VBox * m_showbox

  Area for sequence information.
- Gtk::VBox * m_editbox

  Text-edits and buttons for data.
- Gtk::VBox * m_optsbox

  Reserved for future options.
- Gtk::HBox * m_bottbox

  Holds the Save and Close buttons.
- Gtk::VBox * m_rightbox

  Used for padding on right side.
- Gtk::Button * m_button_del

  "Delete Current Event (*)" button.
- Gtk::Button * m_button_ins

  "Insert New Event" button.
- Gtk::Button * m_button_modify

  "Modify New Event" button.
- Gtk::Button * m_button_save

  "Save to Sequence" button.
- Gtk::Button * m_button_cancel

  "Close" button.
- Gtk::Label * m_label_seq_name

  Items for the inside of the m_showbox member.
- Gtk::Label * m_label_time_sig

  Shows time signature for pattern.
- Gtk::Label * m_label_ppqn

Shows the parts per quarter note.

- Gtk::Label * m_label_channel

  Shows channel number of pattern.

- Gtk::Label * m_label_ev_count

  Shows the count of pattern events.

- Gtk::Label * m_label_spacer

  Spacer for the showbox elements.

- Gtk::Label * m_label_modified

  Shows "[Modified]" if edited.

- Gtk::Label * m_label_category

  Items for the inside of the m_editbox member.

- Gtk::Entry * m_entry_ev_timestamp

  Text edit for event time-stamp.

- Gtk::Entry * m_entry_ev_name

  Text edit for MIDI event name.

- Gtk::Entry * m_entry_ev_data_0

  Text edit for first event datum.

- Gtk::Entry * m_entry_ev_data_1

  Text edit for second event datum.

- Gtk::Label * m_label_time_fmt

  Optsbox item, only "Sequencer64".

- Gtk::Label * m_label_right

  Padding at the right of dialog.

- sequence & m_seq

  A reference to the sequence being edited, to control its editing flag.

- bool m_have_focus

  Indicates that the focus has already been changed to this sequence.

Friends

- class eventslots

Additional Inherited Members

12.11.1 Constructor & Destructor Documentation

12.11.1.1 seq64::eventedit::eventedit (perform & *p*, sequence & *seq*)

We've reordered the pointer members and put them in the initializer list to make the constructor a bit cleaner.

Adjustment parameters:

```
value            initial value
lower            minimum value
upper            maximum value
step_increment   step increment
page_increment   page increment
page_size        page size
```

```
Table constructor parameters:
```

```
        rows
        columns
        homogenous


Table attach() parameters:


        child           widget to add.
        left_attach     column number to attach left side of a child widget
        right_attach    column number to attach right side of a child widget
        top_attach      row number to attach the top of a child widget
        bottom_attach   row number to attach the bottom of a child widget
        xoptions        properties of the child widget when table resized
        yoptions        same as xoptions, except vertical.
        xpadding        padding on L and R of widget added to table
        ypadding        amount of padding above and below the child widget
```

Layout:



Parameters

p	Refers to the main performance object.
seq	Refers to the sequence holding the event data to be edited.

The seqedit class indirectly sets the sequence dirty flags, and this allows the sequence's pattern slot to be updated, which, for example, allows the new experimental in-edit-highlight feature to work. To get the eventedit to also show the in-edit highlighting, we can make the sequence::set_dirty_mp() call. This call does not cause a prompt for saving the file when exiting.

12.11.1.2 seq64::eventedit::~eventedit ( ) [virtual]

We're going to have to run the application through valgrind to make sure that nothing is left behind.

12.11.2 Member Function Documentation

12.11.2.1 void seq64::eventedit::enqueue_draw ( ) [private]

12.11.2.2 void seq64::eventedit::set_seq_title (const std::string & *title*) [private]

Parameters

title	The name of the sequence.

12.11.2.3 void seq64::eventedit::set_seq_time_sig (const std::string & *sig*) [private]

Parameters

sig	The time signature of the sequence.

12.11.2.4 void seq64::eventedit::set_seq_ppqn (const std::string & *p*) [private]

Parameters

p	The parts-per-quarter-note string for the sequence.

12.11.2.5 void seq64::eventedit::set_seq_count ( ) [private]

12.11.2.6 void seq64::eventedit::set_event_category (const std::string & *c*) [private]

Parameters

c	The category string for the current event.

12.11.2.7 void seq64::eventedit::set_event_timestamp (const std::string & *ts*) [private]

Parameters

ts	The time-stamp string for the current event.

12.11.2.8 void seq64::eventedit::set_event_name (const std::string & *n*) [private]

Parameters

n	The name-of-event string for the current event.

12.11.2.9 void seq64::eventedit::set_event_data_0 (const std::string & *d*) [private]

Parameters

d	The first data byte string for the current event.

12.11.2.10 void seq64::eventedit::set_event_data_1 (const std::string & *d*) [private]

Parameters

d	The second data byte string for the current event.

12.11.2.11 void seq64::eventedit::perf_modify ( ) [private]

12.11.2.12 void seq64::eventedit::set_dirty (bool *flag* = true) [private]

This includes changing a label and enabling/disabling the Save button.

Parameters

flag	If true, the modified status is indicated, otherwise it is cleared.

12.11.2.13 void seq64::eventedit::v_adjustment (int *value*) [private]

This function overload provides a common use case.

Parameters

value	The new current value to be indicated by the scroll-bar.

12.11.2.14 void seq64::eventedit::v_adjustment (int *value,* int *lower,* int *upper*) [private]

It keeps the frame scroll-bar in sync with the frame movement actions. Some of the parameters are obtained from the eventslots object:

```
-   Page size comes from eventslots::line_maximum().
-   Page increment is a little less than the page-size value.
```

Parameters

value	The current value to be indicated by the scroll-bar. It will lie between the lower and upper parameter.
lower	The lowest value to be indicated by the scroll-bar.
upper	The highest value to be indicated by the scroll-bar.

12.11.2.15 void seq64::eventedit::change_focus (bool *set_it* = true) [private]

Similar to the same function in seqedit.

Parameters

set_it	If true (the default value), indicates we want focus, otherwise we want to give up focus.

12.11.2.16 void seq64::eventedit::close_out ( ) [private]

12.11.2.17 void seq64::eventedit::handle_close ( ) [private]

Simply calls close_out().

12.11.2.18 void seq64::eventedit::handle_delete ( ) [private]

12.11.2.19 void seq64::eventedit::handle_insert ( ) [private]

The event's location will be determined by the timestamp and existing events. Note that we have to recalibrate the scroll-bar when we insert/delete events by calling v_adjustment().

12.11.2.20 void seq64::eventedit::handle_modify ( ) [private]

Note that there are two cases to worry about. If the timestamp has not changed, then we can simply modify the existing current event in place. Otherwise, we need to delete the old event and insert the new one. But that is done for us by eventslots::modify_current_event().

12.11.2.21 void seq64::eventedit::handle_save ( ) [private]

The event list in the original sequence is cleared, and the editable events are converted to plain events, and added to the container, one by one.

Todo Could also support writing the events to a new sequence, for added flexibility.

12.11.2.22 void seq64::eventedit::handle_cancel ( ) [private]

In order for removing the current-highlighting in the mainwd or perfedit windows, some of the work of handle_close() needs to be done here as well.

12.11.2.23 void seq64::eventedit::on_realize ( ) [private]

Then it sets the vertical adjustment to account for the number of events in the eventslot.

12.11.2.24 void seq64::eventedit::on_set_focus (Widget * *focus*) [private]

Only works in certain circumstances.

Parameters

focus	The widget that has the focus. Merely passed on to gui_window_gtk2's version of this function.

12.11.2.25 bool seq64::eventedit::on_focus_in_event (GdkEventFocus *) [private]

It sets the focus flag and calls change_focus().

12.11.2.26 bool seq64::eventedit::on_focus_out_event (GdkEventFocus *) [private]

It resets the focus flag and calls change_focus().

12.11.2.27 bool seq64::eventedit::on_key_press_event (GdkEventKey * *ev*) [private]

If the Up or Down arrow is pressed (later, k and j :-), then we tell the eventslots object to move the "current event" highlighting up or down. In Gtkmm, these arrows also cause movement from one edit field to the next, so we disable that process if the event was handled here.

Note that some vi-like keys were supported, but they are needed for the edit fields, so cannot be used here. Also, the Delete key is needed for the edit fields. For now, we replace it with the asterisk, which is easy to access from the numeric pad of a keyboard, and allows for rapid deletion. The Insert key also causes confusing effects in the edit fields, so we replace it by the slash. Note that the asterisk and slash should not be required in any of the edit fields.

HOWEVER, "/" still gets passed the edit fields (!), so you'll just have to click the button to insert an event. Let's try the backslash!

Parameters

ev	The key event to process.

Returns

Returns true if the event got handled somewhere along the line.

12.11.2.28 bool seq64::eventedit::on_delete_event (GdkEventAny * *event*) [private]

It sets the sequence object's editing flag to false, and deletes "this". This function is called if the "Close" ("X") button in the window's title bar is clicked. That is a different action from clicking the Close button.

Returns

Always returns false.

12.11.3 Friends And Related Function Documentation

12.11.3.1 friend class eventslots [friend]

12.11.4 Field Documentation

12.11.4.1 Gtk::Table* seq64::eventedit::m_table [private]

Provides the layout table for UI.

12.11.4.2 Gtk::Adjustment* seq64::eventedit::m_vadjust [private]

12.11.4.3 Gtk::VScrollbar* seq64::eventedit::m_vscroll [private]

12.11.4.4 eventslots* seq64::eventedit::m_eventslots [private]

12.11.4.5 Gtk::HBox* seq64::eventedit::m_htopbox [private]

12.11.4.6 Gtk::VBox* seq64::eventedit::m_showbox [private]

12.11.4.7 Gtk::VBox* seq64::eventedit::m_editbox [private]

12.11.4.8 Gtk::VBox* seq64::eventedit::m_optsbox [private]

12.11.4.9 Gtk::HBox* seq64::eventedit::m_bottbox [private]

12.11.4.10 Gtk::VBox* seq64::eventedit::m_rightbox [private]

12.11.4.11 Gtk::Button* seq64::eventedit::m_button_del [private]

12.11.4.12 Gtk::Button* seq64::eventedit::m_button_ins [private]

12.11.4.13 Gtk::Button* seq64::eventedit::m_button_modify [private]

12.11.4.14 Gtk::Button* seq64::eventedit::m_button_save [private]

12.11.4.15 Gtk::Button* seq64::eventedit::m_button_cancel [private]

12.11.4.16 Gtk::Label* seq64::eventedit::m_label_seq_name [private]

Shows the name of the pattern.

12.11.4.17 Gtk::Label* seq64::eventedit::m_label_time_sig [private]

12.11.4.18 Gtk::Label* seq64::eventedit::m_label_ppqn [private]

12.11.4.19 Gtk::Label* seq64::eventedit::m_label_channel [private]

12.11.4.20 Gtk::Label* seq64::eventedit::m_label_ev_count [private]

12.11.4.21 Gtk::Label* seq64::eventedit::m_label_spacer [private]

12.11.4.22 Gtk::Label* seq64::eventedit::m_label_modified [private]

12.11.4.23 Gtk::Label* seq64::eventedit::m_label_category [private]

Shows the type of MIDI event.

12.11.4.24 Gtk::Entry* seq64::eventedit::m_entry_ev_timestamp [private]

12.11.4.25 Gtk::Entry* seq64::eventedit::m_entry_ev_name [private]

12.11.4.26 Gtk::Entry* seq64::eventedit::m_entry_ev_data_0 [private]

12.11.4.27 Gtk::Entry* seq64::eventedit::m_entry_ev_data_1 [private]

12.11.4.28 Gtk::Label* seq64::eventedit::m_label_time_fmt [private]

12.11.4.29 Gtk::Label* seq64::eventedit::m_label_right [private]

12.11.4.30 sequence& seq64::eventedit::m_seq [private]

12.11.4.31 bool seq64::eventedit::m_have_focus [private]

This item is to modify the mainwid and perfedit "edit-sequence" value in order to highlight pattern slot of the pattern/event editor that currently has the user-input focus.

12.12 seq64::eventslots Class Reference

This class implements the left-side list of events in the pattern event-edit window.

Inheritance diagram for seq64::eventslots:



Public Member Functions

- eventslots (perform &p, eventedit &parent, sequence &seq, Gtk::Adjustment &vadjust)

Principal constructor for this user-interface object.

- virtual ~eventslots ()

  Let's provide a do-nothing virtual destructor.

- int event_count () const

  'Getter' function for member m_event_count Returns the number of total events in the sequence represented by the eventslots object.

- int line_count () const

  'Getter' function for member m_line_count Returns the current number of rows (events) in the eventslots's display.

- int line_maximum () const

  'Getter' function for member m_line_maximum Returns the maximum number of rows (events) in the eventslots's display.

- int line_increment () const

  Provides the "page increment" or "line increment" of the frame, This value is the current line-maximum of the frame minus its overlap value.

- int top_index () const

  'Getter' function for member m_top_index

- int current_index () const

  'Getter' function for member m_current_index

- int pager_index () const

  'Getter' function for member m_pager_index

Private Member Functions

- bool load_events ()

  Grabs the event list from the sequence and uses it to fill the editable-event list.

- void set_current_event (const editable_events::iterator ei, int index, bool full_redraw=true)

  Set the current event, which is the event that is highlighted.

- bool insert_event (const editable_event &edev)

  Inserts an event.

- bool insert_event (const std::string &evtimestamp, const std::string &evname, const std::string &evdata0, const std::string &evdata1)

  Inserts an event based on the setting provided, which the eventedit object gets from its Entry fields.

- bool delete_current_event ()

  Deletes the current event, and makes adjustments due to that deletion.

- bool modify_current_event (const std::string &evtimestamp, const std::string &evname, const std::string &evdata0, const std::string &evdata1)

  Modifies the data in the currently-selected event.

- bool save_events ()

  Writes the events back to the sequence.

- void select_event (int event_index=SEQ64_NULL_EVENT_INDEX, bool full_redraw=true)

  Selects and highlights the event that is located in the frame at the given event index.

- void set_text (const std::string &evcategory, const std::string &evtimestamp, const std::string &evname, const std::string &evdata0, const std::string &evdata1)

  Sets the text in the parent dialog, eventedit.

- void enqueue_draw ()

  Wraps queue_draw().

- int convert_y (int y)

  Converts a y-value into an event index relative to 0 (the top of the eventslots window/pixmap) and returns it.

- void draw_event (editable_events::iterator ei, int index)

  Draw the given slot/event.

- void draw_events ()

Draws all of the events in the current eventslots frame.

- void change_vert ()

  Change the vertical offset of events.

- void page_movement (int new_value)

  Adjusts the vertical position of the frame according to the given new scrollbar/vadjust value.

- void page_topper (editable_events::iterator newcurrent)

  Adjusts the vertical position of the frame according to the given new bottom iterator.

- int decrement_top ()

  Decrements the top iterator, if possible.

- int increment_top ()

  Increments the top iterator, if possible.

- int decrement_current ()

  Decrements the current iterator, if possible.

- int increment_current ()

  Increments the current iterator, if possible.

- int decrement_bottom ()

  Decrements the bottom iterator, if possible.

- int increment_bottom ()

  Increments the bottom iterator, if possible.

- void on_realize ()

  Handles the callback when the window is realized.

- bool on_expose_event (GdkEventExpose ∗ev)

  Handles an on-expose event.

- bool on_button_press_event (GdkEventButton ∗ev)

  Provides the callback for a button press, and it handles only a left mouse button.

- bool on_button_release_event (GdkEventButton ∗ev)

  Handles a button-release for the right button, bringing up a popup menu.

- bool on_focus_in_event (GdkEventFocus ∗ev)

  This callback is an attempt to get keyboard focus into the eventslots pixmap area.

- bool on_focus_out_event (GdkEventFocus ∗ev)

  This callback handles an out-of-focus event by resetting the flag HAS_FOCUS.

- bool on_scroll_event (GdkEventScroll ∗ev)

  Handle the scrolling of the window.

- void on_size_allocate (Gtk::Allocation &)

  Handles a size-allocation event.

- void on_move_up ()

  Move to the previous event.

- void on_move_down ()

  Move to the next event.

- void on_frame_up ()

  Move to the previous frame.

- void on_frame_down ()

  Move to the next frame.

- void on_frame_home ()

  Move to the first frame.

- void on_frame_end ()

  Move to the last frame.

Private Attributes

- eventedit & m_parent

  Provides a link to the eventedit that created this object.
- sequence & m_seq

  Provides a reference to the sequence that this dialog is meant to view or modify.
- editable_events m_event_container

  Holds the editable events for this sequence.
- int m_slots_chars

  Provides the number of the characters in the name box.
- int m_char_w

  Provides the "real" width of a character.
- int m_setbox_w

  Provides the width of the "set number" box.
- int m_slots_x

  Provides the width of the names box, which is the width of a character for 24 characters.
- int m_slots_y

  Provides the height of the names box, which is hardwired to 24 pixels.
- int m_event_count

  The current number of events in the edited container.
- int m_line_count

  Counts the number of displayed events, which depends on how many events there are (m_event_count) and the size of the event list (m_line_maximum).
- int m_line_maximum

  Counts the maximum number of displayed events, which depends on the size of the event list (and thus the size of the dialog box for the event editor).
- int m_line_overlap

  Provides a little overlap for paging through the frame.
- int m_top_index

  The index of the event that is 0th in the visible list of events.
- int m_current_index

  Indicates the index of the current event within the frame.
- editable_events::iterator m_top_iterator

  Provides the top "pointer" to the start of the editable-events section that is being shown in the user-interface.
- editable_events::iterator m_bottom_iterator

  Provides the bottom "pointer" to the end of the editable-events section that is being shown in the user-interface.
- editable_events::iterator m_current_iterator

  Provides the "pointer" to the event currently in focus.
- int m_pager_index

  Indicates the event index that matches the index value of the vertical pager.

Friends

- class eventedit

Additional Inherited Members

12.12.1 Constructor & Destructor Documentation

12.12.1.1 seq64::eventslots::eventslots (perform & *p,* eventedit & *parent,* sequence & *seq,* Gtk::Adjustment & *vadjust*)

12.12.1.2 virtual seq64::eventslots::~eventslots ( ) [inline], [virtual]

12.12.2 Member Function Documentation

12.12.2.1 int seq64::eventslots::event_count ( ) const [inline]

12.12.2.2 int seq64::eventslots::line_count ( ) const [inline]

12.12.2.3 int seq64::eventslots::line_maximum ( ) const [inline]

12.12.2.4 int seq64::eventslots::line_increment ( ) const [inline]

12.12.2.5 int seq64::eventslots::top_index ( ) const [inline]

12.12.2.6 int seq64::eventslots::current_index ( ) const [inline]

12.12.2.7 int seq64::eventslots::pager_index ( ) const [inline]

12.12.2.8 bool seq64::eventslots::load_events ( ) [private]

Determines how many events can be shown in the GUI [later] and adjusts the top and bottom editable-event iterators to show the first page of events.

Returns

Returns true if the event iterators were able to be set up as valid.

12.12.2.9 void seq64::eventslots::set_current_event (const editable_events::iterator *ei,* int *index,* bool *full_redraw* = true) [private]

Note in the snprintf() calls that the first digit is part of the data byte, so that translation is easier.

Parameters

ei	The iterator that points to the event.
index	The index (re 0) of the event, starting at the top line of the frame. It is a frame index, not a container index.
full_redraw	If true (the default) does a full redraw of the frame. Otherwise, only the current event is drawn. Generally, the only time a single event (actually, two adjacent events) is convenient to draw is when using the arrow keys, where the speed of keystroke auto-repeats makes the full-frame update scrolling very flickery and disconcerting.

12.12.2.10 bool seq64::eventslots::insert_event (const editable_event & *edev*) [private]

What actually happens here depends if the new event is before the frame, within the frame, or after the frame, based on the timestamp.

If before the frame: To keep the previous events visible, we do not need to increment the iterators (insertion does not affect multimap iterators), but we do need to increment their indices. The contents shown in the frame should not change.

If at the frame top: The new timestamp equals the top timestamp. We don't know exactly where the new event goes in the multimap, but we do have an new event.

If at the frame bottom: TODO

If after the frame: No action needed if the bottom event is actually at the bottom of the frame. But if the frame is not yet filled, we need to increment the bottom iterator, and its index.

Note

Actually, it is far easier to just adjust all the counts and iterators and redraw the screen, as done by the page_topper() function.

Parameters

edev	The event to insert, prebuilt.

Returns

Returns true if the event was inserted.

12.12.2.11 bool seq64::eventslots::insert_event (const std::string & *evtimestamp*, const std::string & *evname*, const std::string & *evdata0*, const std::string & *evdata1*) [private]

It calls the other insert_event() overload.

Note that we need to qualify the temporary event class object we create below, with the seq64 namespace, otherwise the compiler thinks we're trying to access some Gtkmm thing.

Parameters

evtimestamp	The time-stamp of the new event, as obtained from the event-edit timestamp field.
evname	The type name (status name) of the new event, as obtained from the event-edit event-name field.
evdata0	The first data byte of the new event, as obtained from the event-edit data 1 field.
evdata1	The second data byte of the new event, as obtained from the event-edit data 2 field. Used only for two-parameter events.

Returns

Returns true if the event was inserted.

12.12.2.12 bool seq64::eventslots::delete_current_event ( ) [private]

To delete the current event, this function moves the current iterator to the next event, deletes the previously-current iterator, adjusts the event count and the bottom iterator, and redraws the pixmap. The exact changes depend upon whether the deleted event was at the top of the visible frame, within the visible frame, or at the bottom the visible frame. Note that only visible events can be the current event, and thus get deleted.

```
Event Index
 0
 1
 2         Top
 3  <--------- Top case: The new top iterator, index becomes 2
 4
 .
 .         Inside of Visible Frame
 .
43
44         Bottom
45  <--------- Top case: The new bottom iterator, index becomes 44
46             Bottom case: Same result


Basically, when an event is deleted, the frame (delimited by the
event-index members) stays in place, while the frame iterators move to the
previous event.  If the top of the frame would move to before the first
event, then the frame must shrink.

Top case: If the current iterator is the top (of the frame) iterator, then
the top iterator needs to be incremented.  The new top event has the same
index as the now-gone top event. The index of the bottom event is
decremented, since an event before it is now gone.  The bottom iterator
moves to the next event, which is now at the bottom of the frame.  The
current event is treated like the top event.

Inside case: If the current iterator is in the middle of the frame, the top
iterator and index remain unchanged.  The current iterator is incremented,
but its index is now the same as the old bottom index.  Same for the bottom
iterator.

Bottom case: If the current iterator (and bottom iterator) point to the
last event in the frame, then both of them need to be
decremented.  The frame needs to be moved up by one event, so that the
current event remains at the bottom (it's just simpler to manage that way).

If there is no event after the bottom of the frame, the iterators that now
point to end() must backtrack one event.  If the container becomes empty,
then everything is invalidated.
```

Returns

Returns true if the delete was possible. If the container was empty or became empty, then false is returned.

12.12.2.13 bool seq64::eventslots::modify_current_event (const std::string & *evtimestamp,* const std::string & *evname,* const std::string & *evdata0,* const std::string & *evdata1*) [private]

If the timestamp has changed, however, we can't just modify the event in place. Instead, we finish modifying the event, but tell the caller to delete and reinsert the new event (in its proper new location based on timestamp).

This function always copies the original event, modifiies the copy, deletes the original event, and inserts the "new" event into the editable-event container.

Parameters

evtimestamp	Provides the new event time-stamp as edited by the user.
evname	Provides the event name as edited by the user.
evdata0	Provides the first data byte as edited by the user.
evdata1	Provides the second data byte as edited by the user.

Returns

Returns true simply if the event-count is greater than 0.

12.12.2.14 bool seq64::eventslots::save_events ( ) [private]

Also sets the dirty flag for the sequence, via the sequence::add_event() function, but this doesn't seem to set the perform dirty flag. So now we pass the modification buck to the parent, who passes it to the perform object.

We added a copy_events() function in the sequence class to replace add_event() for the purpose of reconstructing the events container for the sequence. It is locked by a mutex, and so will not draw until all is done, preventing a nasty segfault (all segfaults are nasty).

We create a new plain event container here, and then passing it to the new locked/threadsafe sequence::copy_↩ events() function that clears the sequence container and copies the events from the parameter container.

Note that this code will operate event if all events were deleted.

Returns

Returns true if the operations succeeded.

12.12.2.15 void seq64::eventslots::select_event (int *event_index* = SEQ64_NULL_EVENT_INDEX, bool *full_redraw* = true) [private]

The event index is provided by converting the y-coordinate of the mouse pointer into a slot number, and then an event index (actually the slot-distance from the m_top_iterator. Confusing, yes no?

Note that, if the event index is negative, then we just queue up a draw operation, which should paint an empty frame – the event container is empty.

Parameters

event_index	Provides the numeric index of the event in the event frame, or SEQ64_NULL_EVENT if there is no event to draw.
full_redraw	Defaulting to true, this parameter can be set to false in some case to reduce the flickering of the frame under fast movement.

12.12.2.16 void seq64::eventslots::set_text (const std::string & *evcategory*, const std::string & *evtimestamp*, const std::string & *evname*, const std::string & *evdata0*, const std::string & *evdata1*) [private]

Parameters

evcategory	The category of event to be set in the parent.
evtimestamp	The event time-stamp to be set in the parent.
evname	The event name to be set in the parent.
evdata0	The first event data byte to be set in the parent.
evdata1	The second event data byte to be set in the parent.

12.12.2.17 void seq64::eventslots::enqueue_draw ( ) [private]

12.12.2.18 int seq64::eventslots::convert_y (int *y*) [private]

Parameters

y	The y coordinate of the position of the mouse click in the eventslot window/pixmap.

Returns

Returns the index of the event position in the user-interface, which should range from 0 to m_line_count.

12.12.2.19 void seq64::eventslots::draw_event (editable_events::iterator *ei,* int *index*) [private]

The slot contains the event details in (so far) one line of text in the box:

| timestamp | event kind | channel | data 0 name + value | data 1 name + value

Currently, this view shows only events that get copied to the sequence's event list. This rules out the following items from the view:

```
-   MThd (song header)
-   MTrk and Meta TrkEnd (track marker, a sequence has only one track)
-   SeqNr (sequence number)
-   SeqSpec (but there are three that might appear, see below)
-   Meta TrkName
```

The events that are shown in this view are:

```
-   One-data-value events:
    -   Program Change
    -   Channel Pressure
-   Two-data-value events:
    -   Note Off
    -   Note On
    -   Aftertouch
    -   Control Change
    -   Pitch Wheel
-   Other:
    -   SysEx events, with partial show of data bytes
    -   SeqSpec events (TBD):
        -   Key
        -   Scale
        -   Background sequence
```

The index of the event is shown in the editor portion of the eventedit dialog.

12.12.2.20 void seq64::eventslots::draw_events ( ) [private]

It first clears the whole bitmap to white, so that no artifacts from the previous state of the frame are left behind.

Need to figure out how to calculate the number of displayable events.

```
m_line_maximum = ???
```

12.12.2.21 void seq64::eventslots::change_vert ( ) [private]

Note that m_vadjust is the Gtk::Adjustment object that the eventedit parent passes to the gui_drawingarea_gtk2 constructor.

The top-event and bottom-event indices (and their corresponding editable-event iterators) delimit the part of the event container that is displayed in the eventslots user-interface. The top-event index starts at 0, and the bottom-event is larger (initially, by 42 slots).

When the scroll-bar thumb moves up or down, we need to change both event indices and both event iterators by the corresponding amount. Luckily, the std::multimap iterator is bidirectional.

Note that we may need to reduce the movement of events to a value less than a page; it can be limited backwards by the value of the top index, and forward by the value of the bottom index.

12.12.2.22 void seq64::eventslots::page_movement (int *new_value*) [private]

The adjustment is done via movement from the current position.

Do we even need a way to detect excess movement? The scrollbar, if properly set up, should never move the frame too high or too low. Verified by testing.

Parameters

new_value	Provides the new value of the scrollbar position.

12.12.2.23 void seq64::eventslots::page_topper (editable_events::iterator *newcurrent*) [private]

The adjustment is done "from scratch". We've found page movement to be an insoluable problem in some editing circumstances. So now we move to the inserted event, and make it the top event.

However, always moving an inserted event to the top is a bit annoying. So now we backtrack so that the inserted event is at the bottom.

Parameters

newcurrent	Provides the iterator to the event to be shown at the bottom of the frame.

12.12.2.24 int seq64::eventslots::decrement_top ( ) [private]

Returns

Returns 0, or SEQ64_NULL_EVENT_INDEX if the iterator could not be decremented.

12.12.2.25 int seq64::eventslots::increment_top ( ) [private]

Also handles the top-event index, so that the GUI can display the proper event numbers.

Returns

Returns the top index, or SEQ64_NULL_EVENT_INDEX if the iterator could not be incremented, or would increment to the end of the container.

12.12.2.26 int seq64::eventslots::decrement_current ( ) [private]

Returns

Returns the decremented index, or SEQ64_NULL_EVENT_INDEX if the iterator could not be decremented. Remember that the index ranges only from 0 to m_line_count-1, and that is enforced here.

12.12.2.27 int seq64::eventslots::increment_current ( ) [private]

Returns

Returns the incremented index, or SEQ64_NULL_EVENT_INDEX if the iterator could not be incremented. Remember that the index ranges only from 0 to m_line_count-1, and that is enforced here.

12.12.2.28 int seq64::eventslots::decrement_bottom ( ) [private]

Returns

Returns 0, or SEQ64_NULL_EVENT_INDEX if the iterator could not be decremented.

12.12.2.29 int seq64::eventslots::increment_bottom ( ) [private]

There is an issue in paging down using the scrollbar where, at the bottom of the scrolling, the bottom iterator ends up bad. Not yet sure how this happens, so for now we backtrack one event if this happens.

Returns

Returns the incremented index, or SEQ64_NULL_EVENT_INDEX if the iterator could not be incremented.

12.12.2.30 void seq64::eventslots::on_realize ( ) [private]

It first calls the base-class version of on_realize(). Then it allocates any additional resources needed.

12.12.2.31 bool seq64::eventslots::on_expose_event (GdkEventExpose * *ev*) [private]

It draws all of the sequences.

12.12.2.32 bool seq64::eventslots::on_button_press_event (GdkEventButton * *ev*) [private]

12.12.2.33 bool seq64::eventslots::on_button_release_event (GdkEventButton * *ev*) [private]

12.12.2.34 bool seq64::eventslots::on_focus_in_event (GdkEventFocus * *ev*) [private]

See the same function in the perfroll module.

12.12.2.35 bool seq64::eventslots::on_focus_out_event (GdkEventFocus * *ev*) [private]

12.12.2.36 bool seq64::eventslots::on_scroll_event (GdkEventScroll * *ev*) [private]

12.12.2.37 void seq64::eventslots::on_size_allocate (Gtk::Allocation & *a*) [private]

It first calls the base-class version of this function.

12.12.2.38 void seq64::eventslots::on_move_up ( ) [private]

We must scroll up if the event is now before the frame, and should be made the new top event of the frame. Note that this function isn't really an event-response callback. It is called byh eventedit::on_key_press_event().

12.12.2.39 void seq64::eventslots::on_move_down ( ) [private]

We must scroll down if the event is now after the frame. Note that this function isn't really an event-response callback. It is called byh eventedit::on_key_press_event().

12.12.2.40 void seq64::eventslots::on_frame_up ( ) [private]

12.12.2.41 void seq64::eventslots::on_frame_down ( ) [private]

12.12.2.42 void seq64::eventslots::on_frame_home ( ) [private]

12.12.2.43 void seq64::eventslots::on_frame_end ( ) [private]

12.12.3 Friends And Related Function Documentation

12.12.3.1 friend class eventedit [friend]

12.12.4 Field Documentation

12.12.4.1 eventedit& seq64::eventslots::m_parent [private]

12.12.4.2 sequence& seq64::eventslots::m_seq [private]

12.12.4.3 editable_events seq64::eventslots::m_event_container [private]

12.12.4.4 int seq64::eventslots::m_slots_chars [private]

Pretty much hardwired to 64 at present. It helps determine the m_slots_x value (the width of the eventslots list).

12.12.4.5 int seq64::eventslots::m_char_w [private]

This value is obtained from a font-renderer accessor function.

12.12.4.6 int seq64::eventslots::m_setbox_w [private]

This used to be hardwired to $6 * 2$ (character-width times two).

12.12.4.7 int seq64::eventslots::m_slots_x [private]

12.12.4.8 int seq64::eventslots::m_slots_y [private]

This value was once 22 pixels, but we need a little extra room for our new font. This extra room is compatible enough with the old font, as well.

12.12.4.9 int seq64::eventslots::m_event_count [private]

12.12.4.10 int seq64::eventslots::m_line_count [private]

12.12.4.11 int seq64::eventslots::m_line_maximum [private]

12.12.4.12 int seq64::eventslots::m_line_overlap [private]

12.12.4.13 int seq64::eventslots::m_top_index [private]

It is used in numbering the events that are shown in the event-slot frame. Do not confuse it with m_current_index, which is relative to the frame, not the container-beginning.

12.12.4.14 int seq64::eventslots::m_current_index [private]

This event will also be pointed to by the m_current_event iterator. Do not confuse it with m_top_index, which is relative to the container-beginning, not the frame.

12.12.4.15 editable_events::iterator seq64::eventslots::m_top_iterator [private]

12.12.4.16 editable_events::iterator seq64::eventslots::m_bottom_iterator [private]

12.12.4.17 editable_events::iterator seq64::eventslots::m_current_iterator [private]

12.12.4.18 int seq64::eventslots::m_pager_index [private]

12.13 seq64::font Class Reference

This class provides a wrapper for rendering fonts that are encoded as a 16 x 16 pixmap file in XPM format.

Public Types

Public Member Functions

- font ()

  Rote default constructor, except that it does add 1 to the cf_text_h or co_text_h values to use in m_padded_h.
- void init (Glib::RefPtr< Gdk::Window > windo)

  Initialization function for a window on which fonts will be drawn.
- void render_string_on_drawable (Glib::RefPtr< Gdk::GC > m_gc, int x, int y, Glib::RefPtr< Gdk::Drawable > drawable, const char *str, font::Color col) const

  Draws a text string.
- int char_width () const

  'Getter' function for member m_font_w
- int char_height () const

  'Getter' function for member m_font_h
- int padded_height () const

  'Getter' function for member m_padded_h

Private Attributes

- bool m_use_new_font

  If true, use the new font, which is a little bit more modern looking, and is also thicker, and thus a little easier to see.
- int m_cell_w

  Specifies the cell width of the whole character cell.
- int m_cell_h

  Specfies the cell height of the whole character cell.
- int m_font_w

  Specifies the exact width of a character cell, in pixels.
- int m_font_h

  Specifies the exact height of a character cell, in pixels.
- int m_offset

  Provides an ad hoc small horizontal or vertical offset for printing strings.
- int m_padded_h

  Provides a common constant used by much of the drawing code, but only marginally related to the padded character height.
- const Glib::RefPtr< Gdk::Pixmap > * m_pixmap

  Points to the current pixmap (m_black_pixmap or m_white_pixmap) to use to render a string.
- Glib::RefPtr< Gdk::Pixmap > m_black_pixmap

  The pixmap in the file `src/pixmaps/font_b.xpm` is loaded into this object.
- Glib::RefPtr< Gdk::Pixmap > m_white_pixmap

  The pixmap in the file `src/pixmaps/font_w.xpm` is loaded into this object.
- Glib::RefPtr< Gdk::Pixmap > m_b_on_y_pixmap

  The pixmap in the file `src/pixmaps/font_y.xpm` is loaded into this object.
- Glib::RefPtr< Gdk::Pixmap > m_y_on_b_pixmap

  The pixmap in the file `src/pixmaps/font_yb.xpm` is loaded into this object.
- Glib::RefPtr< Gdk::Pixmap > m_b_on_c_pixmap

  The pixmap in the file `src/pixmaps/cyan_wenfont_y.xpm` is loaded into this object.
- Glib::RefPtr< Gdk::Pixmap > m_c_on_b_pixmap

  The pixmap in the file `src/pixmaps/cyan_wenfont_yb.xpm` is loaded into this object.
- Glib::RefPtr< Gdk::Bitmap > m_clip_mask

  This object is instantiated as a default object.

12.13.1 Member Enumeration Documentation

12.13.1.1 enum seq64::font::Color

Basically, these two values cause the selection of one or another pixmap (font_b_xpm and font_w_xpm). We've added two more pixmaps to draw black text on a yellow background (font_y.xpm) and yellow text on a black background (font_yb.xpm). Oh, and couple more for cyan and black text-blitting.

Enumerator

BLACK The first supported color. A black font on a white background.

WHITE The second supported color. A white font on a black background.

BLACK_ON_YELLOW A new color, for drawing black text on a yellow background.

YELLOW_ON_BLACK A new color, for drawing yellow text on a black background.

BLACK_ON_CYAN A new color, for drawing black text on a cyan background.

CYAN_ON_BLACK A new color, for drawing cyan text on a black background.

12.13.2 Constructor & Destructor Documentation

12.13.2.1 seq64::font::font ( )

12.13.3 Member Function Documentation

12.13.3.1 void seq64::font::init (Glib::RefPtr< Gdk::Window > *wp*)

This function loads four pixmaps that contain the characters to be used to draw text strings.

One pixmap has white characters on a black background, one has black characters on a white background, one has yellow characters on a black background, and one has black characters on a yellow background.

Parameters

wp	Provides the windows pointer for the window that holds the color map.

12.13.3.2 void seq64::font::render_string_on_drawable (Glib::RefPtr< Gdk::GC > *gc*, int *x*, int *y*, Glib::RefPtr< Gdk::Drawable > *a_draw*, const char * *str*, font::Color *col*) const

This function grabs the proper font bitmap, extracts the current character pixmap from it, and slaps it down where it needs to be to render the character in the string.

Parameters

gc	Provides the graphics context for drawing the text using GTK+.
x	The horizontal location of the text.
y	The vertical location of the text.
a_draw	The drawable object on which to draw the text.
str	The string to draw. Should use a constant string reference instead.

Parameters

col	The font color to use to draw the string. The supported values are font::BLACK, font::WHITE, font::BLACK_ON_YELLOW, font::YELLOW_ON_BLACK. The actual correct colors are provided by selecting one of four font pixmaps, as described in the init() function.

12.13.3.3 int seq64::font::char_width ( ) const [inline]

12.13.3.4 int seq64::font::char_height ( ) const [inline]

12.13.3.5 int seq64::font::padded_height ( ) const [inline]

12.13.4 Field Documentation

12.13.4.1 bool seq64::font::m_use_new_font [private]

12.13.4.2 int seq64::font::m_cell_w [private]

12.13.4.3 int seq64::font::m_cell_h [private]

12.13.4.4 int seq64::font::m_font_w [private]

Currently defaults to cf_text_w = 6. Note that a lot of stuff depends on this being 6 at present, even with our new, slightly wider, font.

12.13.4.5 int seq64::font::m_font_h [private]

Currently defaults to cf_text_h = 10. Note that a lot of stuff depends on this being 10 at present, even with our new, slightly wider, font. But some of the drawing code doesn't use the character height, but the padded character height.

12.13.4.6 int seq64::font::m_offset [private]

12.13.4.7 int seq64::font::m_padded_h [private]

12.13.4.8 const Glib::RefPtr<Gdk::Pixmap>* seq64::font::m_pixmap [mutable], [private]

This member used to be an object, but it's probably a bit faster to just use a pointer (or a reference).

12.13.4.9 Glib::RefPtr<Gdk::Pixmap> seq64::font::m_black_pixmap [private]

It contains a black font on a white background. The new-style font, if selected, is in the `resources/pixmaps/wenfont_b.xmp` pixmap.

12.13.4.10 Glib::RefPtr<Gdk::Pixmap> seq64::font::m_white_pixmap [private]

It contains a black font on a white background. The new-style font, if selected, is in the `resources/pixmaps/wenfont_w.xmp` pixmap.

12.13.4.11 Glib::RefPtr<Gdk::Pixmap> seq64::font::m_b_on_y_pixmap [private]

It contains a black font on a yellow background. The new-style font, if selected, is in the `resources/pixmaps/wenfont_y.xmp` pixmap.

12.13.4.12 Glib::RefPtr<Gdk::Pixmap> seq64::font::m_y_on_b_pixmap [private]

It contains a yellow font on a black background. The new-style font, if selected, is `resources/pixmaps/wenfont_yb.xmp` pixmap.

12.13.4.13 Glib::RefPtr<Gdk::Pixmap> seq64::font::m_b_on_c_pixmap [private]

It contains a black font on a cyan background. It is available only for the new font-style.

12.13.4.14 Glib::RefPtr<Gdk::Pixmap> seq64::font::m_c_on_b_pixmap [private]

It contains a cyan font on a black background. It is available only for the new font-style.

12.13.4.15 Glib::RefPtr<Gdk::Bitmap> seq64::font::m_clip_mask [private]

All we know is it seems to be a requirement for creating a pixmap object from an XMP file.

12.14 seq64::FruityPerfInput Class Reference

Implements the performance input of that certain fruity sequencer that people seem to like.

Inheritance diagram for seq64::FruityPerfInput:



Public Member Functions

- FruityPerfInput ()

  Default constructor.
- bool on_button_press_event (GdkEventButton ∗ev, perfroll &roll)

  Handles a button-press event in the Fruity manner.
- bool on_button_release_event (GdkEventButton ∗ev, perfroll &roll)

  Handles a button-release event.
- bool on_motion_notify_event (GdkEventMotion ∗ev, perfroll &roll)

  Handles a Fruity motion-notify event.

Private Member Functions

- void update_mouse_pointer (perfroll &roll)

  Updates the mouse pointer, implementing a context-sensitive mouse.
- bool on_left_button_pressed (GdkEventButton ∗ev, perfroll &roll)

  Handles the left button of the mouse.
- bool on_right_button_pressed (GdkEventButton ∗ev, perfroll &roll)

  Handles the right button of the mouse.

Private Attributes

- long m_current_x

  The current x value of the mouse.
- long m_current_y

  The current y value of the mouse.

Friends

- class perfroll

Additional Inherited Members

12.14.1 Constructor & Destructor Documentation

12.14.1.1 seq64::FruityPerfInput::FruityPerfInput ( ) [inline]

12.14.2 Member Function Documentation

12.14.2.1 bool seq64::FruityPerfInput::on_button_press_event (GdkEventButton * *ev*, perfroll & *roll*) [virtual]

Parameters

ev	The button-press event to process.
roll	The song editor piano roll that is the "parent" of this class.

Returns

Returns true if a modification occurred.

Implements seq64::AbstractPerfInput.

12.14.2.2 bool seq64::FruityPerfInput::on_button_release_event (GdkEventButton * *ev*, perfroll & *roll*) [virtual]

Why is m_adding_pressed modified conditionally when the same modification is then made unconditionally?

Parameters

ev	The button-release event to process.
roll	The song editor piano roll that is the "parent" of this class.

Returns

Returns true if a modification occurred.

Implements seq64::AbstractPerfInput.

12.14.2.3 bool seq64::FruityPerfInput::on_motion_notify_event (GdkEventMotion * *ev*, perfroll & *roll*) [virtual]

Parameters

ev	The motion-notify event to process.
roll	The song editor piano roll that is the "parent" of this class.

Returns

Returns true if a modification occurred, and sets the perform modified flag based on that result.

Implements seq64::AbstractPerfInput.

12.14.2.4 void seq64::FruityPerfInput::update_mouse_pointer (perfroll & *roll*) [private]

Note that perform::convert_xy() returns its values via side-effects on the last two parameters.

Parameters

roll	The song editor piano roll that is the "parent" of this class.

12.14.2.5 bool seq64::FruityPerfInput::on_left_button_pressed (GdkEventButton * *ev*, perfroll & *roll*) [private]

It can handle splitting triggers (?), adding notes, and the following clicks to resize the event, or move it, depending on where clicked:

```
-   clicked left side: begin a grow/shrink for the left side
-   clicked right side: grow/shrink the right side
-   clicked in the middle - move it
```

I don't get it, though... all three buttons are handled in the generic button-press callback. Oh, this is just a helper function.

Parameters

ev	The left-button-press event to process.
roll	The song editor piano roll that is the "parent" of this class.

Returns

Now returns true if a modification occurred.

12.14.2.6 bool seq64::FruityPerfInput::on_right_button_pressed (GdkEventButton * *ev*, perfroll & *roll*) [private]

I don't get it, though... all three buttons are handled in the generic button-press callback. Oh, this is a helper function.

Parameters

ev	The right-button-press event to process.
roll	The song editor piano roll that is the "parent" of this class.

Returns

Returns true if a modification occurred.

12.14.3 Friends And Related Function Documentation

12.14.3.1 friend class perfroll [friend]

12.14.4 Field Documentation

12.14.4.1 long seq64::FruityPerfInput::m_current_x [private]

12.14.4.2 long seq64::FruityPerfInput::m_current_y [private]

12.15 seq64::FruitySeqEventInput Struct Reference

This structure implements the interaction methods for the "fruity" mode of operation.

Public Member Functions

- FruitySeqEventInput ()

  Default constructor.
- void update_mouse_pointer (seqevent &ths)

  Provides support for a context-sensitive mouse.
- bool on_button_press_event (GdkEventButton *ev, seqevent &ths)

  Implements the on-button-press event callback.
- bool on_button_release_event (GdkEventButton *ev, seqevent &ths)

  Implements the on-button-release callback.
- bool on_motion_notify_event (GdkEventMotion *ev, seqevent &ths)

  Implements the on-motion-notify callback.

Data Fields

- bool m_justselected_one

  Indicates that the left mouse button was click to start a selection.
- bool m_is_drag_pasting_start

  Set to true when the mouse button is pressed and we're starting to drag some notes to move them and paste them to a different location.
- bool m_is_drag_pasting

  Set to true when the left mouse button is pressed for dragging and pasting, set to false when the mouse button is released to drop the pasted items.

12.15.1 Constructor & Destructor Documentation

12.15.1.1 seq64::FruitySeqEventInput::FruitySeqEventInput ( ) [inline]

12.15.2 Member Function Documentation

12.15.2.1 void seq64::FruitySeqEventInput::update_mouse_pointer (seqevent & *seqev*)

Parameters

seqev	Provides the seqevent pane (actually a strip on the seqedit window) to update to show the proper mouse cursor (left pointer, center pointer, and pencil).

12.15.2.2 bool seq64::FruitySeqEventInput::on_button_press_event (GdkEventButton * *ev,* seqevent & *seqev*)

Handles dragging and other actions.

The first thing is to set the values for dragging, then reset the box that holds the dirty redraw spot. If pasting, undo the clipboard, and paste the selected events.

Otherwise, process the mouse actions. The current steps shown below are my initial guesses, to be verified at some point.

1. Left button:
   (a) Click:
      i. A click and release without a drag, or without a Ctrl-Shift, deselects the events.
      ii. A direct click on an event selects only that event.
   (b) Click-drag:
      i. If events already selected, adds note and length to the selected notes.
      ii. Otherwise, select the notes and events.
      iii. If no events selected in the end, undo the selection.

- Ctrl-left button:

Parameters

ev	The button event for the press of a mouse button.
seqev	Provides the seqevent strip to be affected by this button event.

Returns

Returns true if a modification was made. It used to return true all the time.

12.15.2.3 bool seq64::FruitySeqEventInput::on_button_release_event (GdkEventButton * *ev,* seqevent & *seqev*)

Parameters

ev	The button event for the press of a mouse button.
seqev	Provides the seqevent strip to be affected by this button event.

Returns

Returns true if a modification was made. It used to return true all the time.

12.15.2.4 bool seq64::FruitySeqEventInput::on_motion_notify_event (GdkEventMotion * *ev*, seqevent & *seqev*)

Parameters

ev	The button event for the press of a mouse button.
seqev	Provides the seqevent strip to be affected by this button event.

Returns

Returns true if a modification occurred, and sets the perform modified flag based on that result.

12.15.3 Field Documentation

12.15.3.1 bool seq64::FruitySeqEventInput::m_justselected_one

12.15.3.2 bool seq64::FruitySeqEventInput::m_is_drag_pasting_start

12.15.3.3 bool seq64::FruitySeqEventInput::m_is_drag_pasting

12.16 seq64::FruitySeqRollInput Class Reference

Implements the fruity mouse interaction paradigm for the seqroll.

Public Member Functions

- FruitySeqRollInput ()
  Default constructor.
- void update_mouse_pointer (seqroll &ths)
  Updates the mouse pointer, implementing a context-sensitive mouse.
- bool on_button_press_event (GdkEventButton *ev, seqroll &ths)
  Implements the fruity on-button-press callback.
- bool on_button_release_event (GdkEventButton *ev, seqroll &ths)
  Implements the fruity handling for the on-button-release event.
- bool on_motion_notify_event (GdkEventMotion *ev, seqroll &ths)
  Implements the fruity handling for the on-motion-notify event.

Private Attributes

- bool m_erase_painting
  Set to tru if we hold the right mouse button down (in "fruity" mode) and start to drag the mouse around, erasing notes.
- int m_drag_paste_start_pos [2]
  Holds the original position of the mouse when ctrl-left-click-drag is done, and is used to make sure that the action doesn't occur until a movement of at least 6 pixels has occurred, to avoid unintended actions caused by minimal jitter in the user's hands.

12.16.1 Constructor & Destructor Documentation

12.16.1.1 seq64::FruitySeqRollInput::FruitySeqRollInput ( ) [inline]

12.16.2 Member Function Documentation

12.16.2.1 void seq64::FruitySeqRollInput::update_mouse_pointer (seqroll & *sroll*)

Parameters

sroll	Provides the "parent" of this interaction class.

12.16.2.2 bool seq64::FruitySeqRollInput::on_button_press_event (GdkEventButton * *ev*, seqroll & *sroll*)

This function now uses the needs_update flag to determine if the perform object should modify().

Parameters

ev	The button event.
sroll	The parent of this "fruity" interaction class.

Returns

Returns the value of needs_update. It used to return only true.

12.16.2.3 bool seq64::FruitySeqRollInput::on_button_release_event (GdkEventButton * *ev*, seqroll & *sroll*)

Parameters

ev	The button event.
sroll	The parent of this "fruity" interaction class.

Returns

Returns the value of needs_update. It used to return only true.

If in moving mode, adjust for snap and convert deltas into screen coordinates. Since delta_note was from delta_y, it will be flipped (delta_y[0] = note[127], etc.), so we have to adjust.

12.16.2.4 bool seq64::FruitySeqRollInput::on_motion_notify_event (GdkEventMotion * *ev*, seqroll & *sroll*)

Parameters

ev	The motion event.
sroll	The parent of this "fruity" interaction class. (Why not just inherit and save all these indirect accesses to the seqroll? Well, that would make it more difficult to change the mode of interation, in the Options menu, on the fly.)

Returns

Returns the value of needs_update.

In "fruity" interatction mode, ctrl-left-click-drag on selected note(s) starts a copy/unselect/paste. Doesn't begin the paste until the mouse moves a few pixels, to filter out the unsteady hand.

12.16.3 Field Documentation

12.16.3.1 bool seq64::FruitySeqRollInput::m_erase_painting [private]

12.16.3.2 int seq64::FruitySeqRollInput::m_drag_paste_start_pos[2] [private]

12.17 seq64::gui_assistant Class Reference

This class provides an interface for some of the GUI support needed in Sequencer64.

Inheritance diagram for seq64::gui_assistant:



Public Member Functions

- gui_assistant (keys_perform &kp)

  This constructor wires in some externally (for now) created objects.
- virtual ~gui_assistant ()

  Stock base-class implementation of a virtual destructor.
- virtual void quit ()=0
- virtual void jack_idle_connect (jack_assistant &jack)=0
- virtual void lash_timeout_connect (lash *lashobject)=0
- const keys_perform & keys () const

  'Getter' function for member m_keys_perform The const getter.
- keys_perform & keys ()

  'Getter' function for member m_keys_perform The un-const getter.

Private Attributes

- keys_perform & m_keys_perform

  Provides a reference to the app-specific GUI-specific keys_perform-derived object that an application is going to use for handling sequence-control keys.

12.17.1 Detailed Description

It also contain a number of helper objects that all kind of go together; only this assistant object will need to be passed around (by non-GUI code).

12.17.2 Constructor & Destructor Documentation

12.17.2.1 seq64::gui_assistant::gui_assistant (keys_perform & *kp*)

Parameters

kp	Provides a set of key codes to be used by the perform object to control patterns and their performance.

12.17.2.2 virtual seq64::gui_assistant::~gui_assistant ( ) [inline], [virtual]

12.17.3 Member Function Documentation

12.17.3.1 virtual void seq64::gui_assistant::quit ( ) [pure virtual]

Implemented in seq64::gui_assistant_gtk2.

12.17.3.2 virtual void seq64::gui_assistant::jack_idle_connect (jack_assistant & *jack*) [pure virtual]

Implemented in seq64::gui_assistant_gtk2.

12.17.3.3 virtual void seq64::gui_assistant::lash_timeout_connect (lash * *lashobject*) [pure virtual]

Implemented in seq64::gui_assistant_gtk2.

12.17.3.4 const keys_perform& seq64::gui_assistant::keys ( ) const [inline]

12.17.3.5 keys_perform& seq64::gui_assistant::keys ( ) [inline]

12.17.4 Field Documentation

12.17.4.1 keys_perform& seq64::gui_assistant::m_keys_perform [private]

12.18 seq64::gui_assistant_gtk2 Class Reference

This class provides an interface for some of the Gtk/Gdk/Glib support needed in Sequencer64.

Inheritance diagram for seq64::gui_assistant_gtk2:



Public Member Functions

- gui_assistant_gtk2 ()

  This class provides an interface for some of the Gtk/Gdk/Glib support needed in Sequencer64.
- virtual ~gui_assistant_gtk2 ()

  Virtual classes require a virtual destructor.
- virtual void quit ()

  Calls the Glib Main object's quit() function.
- virtual void lash_timeout_connect (lash *lashobject)

  Connects the LASH timeout-event callback to the Glib timeout object.
- virtual void jack_idle_connect (jack_assistant &jack)

  Connects the JACK session-event callback to the Glib idle object.

Static Private Attributes

- static keys_perform_gtk2 sm_internal_keys

  Provides a pre-made keys_perform object.

12.18.1 Constructor & Destructor Documentation

12.18.1.1 seq64::gui_assistant_gtk2::gui_assistant_gtk2 ( )

12.18.1.2 virtual seq64::gui_assistant_gtk2::~gui_assistant_gtk2 ( ) [inline], [virtual]

12.18.2 Member Function Documentation

12.18.2.1 void seq64::gui_assistant_gtk2::quit ( ) [virtual]

Implements seq64::gui_assistant.

12.18.2.2 void seq64::gui_assistant_gtk2::lash_timeout_connect (lash * *lashobject*) [virtual]

The time-out value is set to 250 ms.

Implements seq64::gui_assistant.

12.18.2.3 void seq64::gui_assistant_gtk2::jack_idle_connect (jack_assistant & *jack*) [virtual]

If JACK session support is not enabled, we might emit a message. This mainly prevents a compiler warning about an unused parameter.

Implements seq64::gui_assistant.

12.18.3 Field Documentation

12.18.3.1 keys_perform_gtk2 seq64::gui_assistant_gtk2::sm_internal_keys [static], [private]

This object is set into the reference provided in the gui_assistant base class.

12.19 seq64::gui_drawingarea_gtk2 Class Reference

Implements the basic drawing areas of the application.

Inheritance diagram for seq64::gui_drawingarea_gtk2:



Data Structures

- struct rect

  A small helper structure representing a rectangle.

Public Member Functions

- gui_drawingarea_gtk2 (perform &p, int window_x=0, int window_y=0)

  Perform-only constructor.
- gui_drawingarea_gtk2 (perform &a_perf, Gtk::Adjustment &a_hadjust, Gtk::Adjustment &a_vadjust, int window_x=0, int window_y=0)

  Principal constructor.
- virtual ~gui_drawingarea_gtk2 ()

  Provides a destructor to delete allocated objects.
- int window_x () const

  'Getter' function for member m_window_x
- int window_y () const

  'Getter' function for member m_window_y
- int current_x () const

  'Getter' function for member m_current_x
- int current_y () const

  'Getter' function for member m_current_y
- int drop_x () const

  'Getter' function for member m_drop_x
- int drop_y () const

  'Getter' function for member m_drop_y

Protected Member Functions

- virtual void force_draw ()

  Provides a common function for redrawing.
- perform & perf ()

  'Getter' function for member m_mainperf
- void clear_window ()

  Clears the main window.
- void set_line (Gdk::LineStyle ls, int width=1)

  A small wrapper function for readability in line-drawing.
- void draw_line (int x1, int y1, int x2, int y2)

  A small wrapper function to draw a line on the window.
- void draw_line (const Color &c, int x1, int y1, int x2, int y2)

  A small wrapper function to draw a line on the window after setting the given foreground color.
- void draw_line_on_pixmap (int x1, int y1, int x2, int y2)

  A small wrapper function to draw a line on the pixmap.
- void draw_line_on_pixmap (const Color &c, int x1, int y1, int x2, int y2)

  A small wrapper function to draw a line on the pixmap after setting the given foreground color.
- void draw_line (Glib::RefPtr< Gdk::Pixmap > &pixmap, int x1, int y1, int x2, int y2)

  A small wrapper function to draw a line on any pixmap (not a drawable, though, due to a compiler error after setting the given foreground color.
- void draw_line (Glib::RefPtr< Gdk::Pixmap > &pixmap, const Color &c, int x1, int y1, int x2, int y2)

  A small wrapper function to draw a line on the pixmap after setting the given foreground color.
- void draw_line (Glib::RefPtr< Gdk::Drawable > &drawable, int x1, int y1, int x2, int y2)

  A small wrapper function to draw a line on any pixmap (not a drawable, though, due to a compiler error after setting the given foreground color.
- void draw_line (Glib::RefPtr< Gdk::Drawable > &drawable, const Color &c, int x1, int y1, int x2, int y2)

  A small wrapper function to draw a line on the drawable after setting the given foreground color.
- void render_string (int x, int y, const std::string &s, font::Color color)

  A small wrapper function for readability in string-drawing to the window.
- void render_string_on_pixmap (int x, int y, const std::string &s, font::Color color)

  A small wrapper function for readability in string-drawing to the pixmap.
- void draw_rectangle (int x, int y, int lx, int ly, bool fill=true)

  A small wrapper function for readability in box-drawing on the window.
- void draw_rectangle (const Color &c, int x, int y, int lx, int ly, bool fill=true)

  A small wrapper function for readability in box-drawing.
- void draw_rectangle (Glib::RefPtr< Gdk::Drawable > &drawable, int x, int y, int lx, int ly, bool fill=true)

  A small wrapper function for readability in box-drawing on a "drawable" context, where the foreground color has already been specified.
- void draw_rectangle (Glib::RefPtr< Gdk::Drawable > &drawable, const Color &c, int x, int y, int lx, int ly, bool fill=true)

  A small wrapper function for readability in box-drawing on any drawable context.
- void draw_rectangle (Glib::RefPtr< Gdk::Pixmap > &pixmap, int x, int y, int lx, int ly, bool fill=true)

  A small wrapper function for readability in box-drawing on a "pixmap" context, where the foreground color has already been specified.
- void draw_rectangle (Glib::RefPtr< Gdk::Pixmap > &pixmap, const Color &c, int x, int y, int lx, int ly, bool fill=true)

  A small wrapper function for readability in box-drawing on any pixmap context.
- void draw_rectangle_on_pixmap (int x, int y, int lx, int ly, bool fill=true)

  A small wrapper function for readability in box-drawing on the pixmap.
- void draw_rectangle_on_pixmap (const Color &c, int x, int y, int lx, int ly, bool fill=true)

  A small wrapper function for readability in box-drawing on the pixmap.

- void draw_normal_rectangle_on_pixmap (int x, int y, int lx, int ly, bool fill=true)

  A small wrapper function for readability in box-drawing on the pixmap.
- void draw_drawable (int xsrc, int ysrc, int xdest, int ydest, int width, int height)

  Provides the most common use case for redrawing.
- void scroll_hadjust (Gtk::Adjustment &hadjust, double step)

  This function provides optimization for the on_scroll_event() functions, and should provide support for having the seqedit/seqroll/seqtime/seqdata panes follow the scrollbar, in a future upgrade (now partly in place).
- void scroll_vadjust (Gtk::Adjustment &vadjust, double step)

  This function is the vertical version of the scroll_hadjust() function, intended for adding keystroke vertical scrolling using the Page-Up and Page-Down keys, as a new feature of Sequencer64.
- void scroll_hset (Gtk::Adjustment &hadjust, double value)
- void scroll_vset (Gtk::Adjustment &vadjust, double value)
- void set_current_drop_x (int x)

  Sets the current x value and the drop x value.
- void set_current_drop_y (int y)

  Sets the current y value and the drop y value.
- void on_realize ()

  For this GTK callback, on realization of window, initialize the shiz.

Protected Attributes

- Glib::RefPtr< Gdk::GC > m_gc

  The graphics context, which is required for ever drawing and rendering operation.
- Glib::RefPtr< Gdk::Window > m_window

  Provides the default "window".
- Gtk::Adjustment & m_vadjust

  Provides an object for vertical "adjustments".
- Gtk::Adjustment & m_hadjust

  Provides an object for horizontal "adjustments".
- Glib::RefPtr< Gdk::Pixmap > m_pixmap

  Provides the default "pixmap".
- Glib::RefPtr< Gdk::Pixmap > m_background

  Another pixmap, used for backgrounds.
- Glib::RefPtr< Gdk::Pixmap > m_foreground

  Another pixmap, used for foregrounds.
- perform & m_mainperf

  A frequent hook into the main perform object.
- int m_window_x

  Window sizes.
- int m_window_y

  Window height value.
- int m_current_x

  The x and y value of the current location of the mouse (during dragging?)
- int m_current_y

  Current mouse y value.
- int m_drop_x

  These values are used when roping and highlighting a bunch of events.
- int m_drop_y

  Current mouse y-drop value.

Private Member Functions

- gui_drawingarea_gtk2 (const gui_drawingarea_gtk2 &)
- gui_drawingarea_gtk2 & operator= (const gui_drawingarea_gtk2 &)
- void gtk_drawarea_init ()

  Does basic initialization for each of the constructors.

Additional Inherited Members

12.19.1 Detailed Description

Note that this class really "isn't" a gui_pallete_gtk2; it should simply "have" one. But that base class must be derived from Gtk::DrawingArea. We don't want to waste some space by using a "has-a" relationship, and also put up with having to access the palette indirectly. So, in this case, we tolerate the less strict implementation.

12.19.2 Constructor & Destructor Documentation

12.19.2.1 seq64::gui_drawingarea_gtk2::gui_drawingarea_gtk2 (const gui_drawingarea_gtk2 &) [private]

12.19.2.2 seq64::gui_drawingarea_gtk2::gui_drawingarea_gtk2 (perform & *p*, int *window_x* = 0, int *window_y* = 0)

12.19.2.3 seq64::gui_drawingarea_gtk2::gui_drawingarea_gtk2 (perform & *a_perf*, Gtk::Adjustment & *a_hadjust*, Gtk::Adjustment & *a_vadjust*, int *window_x* = 0, int *window_y* = 0)

12.19.2.4 seq64::gui_drawingarea_gtk2::~gui_drawingarea_gtk2 ( ) [virtual]

12.19.3 Member Function Documentation

12.19.3.1 gui_drawingarea_gtk2& seq64::gui_drawingarea_gtk2::operator= (const gui_drawingarea_gtk2 &) [private]

12.19.3.2 int seq64::gui_drawingarea_gtk2::window_x ( ) const [inline]

12.19.3.3 int seq64::gui_drawingarea_gtk2::window_y ( ) const [inline]

12.19.3.4 int seq64::gui_drawingarea_gtk2::current_x ( ) const [inline]

12.19.3.5 int seq64::gui_drawingarea_gtk2::current_y ( ) const [inline]

12.19.3.6 int seq64::gui_drawingarea_gtk2::drop_x ( ) const [inline]

12.19.3.7 int seq64::gui_drawingarea_gtk2::drop_y ( ) const [inline]

12.19.3.8 virtual void seq64::gui_drawingarea_gtk2::force_draw ( ) [inline], [protected], [virtual]

This function forces a redraw. Some classes extend this function.

Reimplemented in seq64::seqroll, seq64::seqevent, and seq64::seqkeys.

12.19.3.9 perform& seq64::gui_drawingarea_gtk2::perf ( ) [inline], [protected]

12.19.3.10 void seq64::gui_drawingarea_gtk2::clear_window ( ) [inline], [protected]

One less need to access m_window directly.

12.19.3.11 void seq64::gui_drawingarea_gtk2::set_line (Gdk::LineStyle *ls*, int *width* = 1) [inline], [protected]

Sets the attributes of a line to be drawn.

Parameters

ls	Provides the Gtk-specific line style.
width	Provides the width of the line to be drawn. It defaults to the most common value, 1.

12.19.3.12 void seq64::gui_drawingarea_gtk2::draw_line (int *x1*, int *y1*, int *x2*, int *y2*) [inline], [protected]

Parameters

x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.19.3.13 void seq64::gui_drawingarea_gtk2::draw_line (const Color & *c*, int *x1*, int *y1*, int *x2*, int *y2*) [protected]

Parameters

c	The foreground color in which to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.19.3.14 void seq64::gui_drawingarea_gtk2::draw_line_on_pixmap (int *x1*, int *y1*, int *x2*, int *y2*) [inline], [protected]

Parameters

x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.19.3.15 void seq64::gui_drawingarea_gtk2::draw_line_on_pixmap (const Color & *c*, int *x1*, int *y1*, int *x2*, int *y2*) [protected]

Parameters

c	The foreground color in which to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.19.3.16 void seq64::gui_drawingarea_gtk2::draw_line (Glib::RefPtr< Gdk::Pixmap > & *pixmap*, int *x1*, int *y1*, int *x2*, int *y2*) [inline], [protected]

Parameters

pixmap	Provides the Gdk::Pixmap pointer needed to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.19.3.17 void seq64::gui_drawingarea_gtk2::draw_line (Glib::RefPtr< Gdk::Pixmap > & *pixmap*, const Color & *c*, int *x1*, int *y1*, int *x2*, int *y2*) [protected]

Parameters

pixmap	Provides the Gdk::Drawable pointer needed to draw the line.
c	The foreground color in which to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.19.3.18 void seq64::gui_drawingarea_gtk2::draw_line (Glib::RefPtr< Gdk::Drawable > & *drawable*, int *x1*, int *y1*, int *x2*, int *y2*) [inline], [protected]

Parameters

drawable	Provides the Gdk::Drawable pointer needed to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.19.3.19 void seq64::gui_drawingarea_gtk2::draw_line (Glib::RefPtr< Gdk::Drawable > & *drawable*, const Color & *c*, int *x1*, int *y1*, int *x2*, int *y2*) [protected]

Parameters

drawable	Provides the Gdk::Drawable pointer needed to draw the line.
c	The foreground color in which to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.19.3.20 void seq64::gui_drawingarea_gtk2::render_string (int *x*, int *y*, const std::string & *s*, font::Color *color*) [inline], [protected]

Parameters

x	The x-coordinate of the origin.
y	The y-coordinate of the origin.
s	The string to be drawn.
color	The color with which to draw the string.

12.19.3.21 void seq64::gui_drawingarea_gtk2::render_string_on_pixmap (int *x*, int *y*, const std::string & *s*, font::Color *color*) [inline], [protected]

Parameters

x	The x-coordinate of the origin.
y	The y-coordinate of the origin.
s	The string to be drawn.
color	The color with which to draw the string.

12.19.3.22 void seq64::gui_drawingarea_gtk2::draw_rectangle (int *x*, int *y*, int *lx*, int *ly*, bool *fill* = true) [inline], [protected]

Parameters

x	The x-coordinate of the origin.
y	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults to true.

12.19.3.23 void seq64::gui_drawingarea_gtk2::draw_rectangle (const Color & *c*, int *x*, int *y*, int *lx*, int *ly*, bool *fill* = true) [protected]

It adds setting the foreground color to the draw_rectangle() function.

Parameters

c	Provides the foreground color to set.
x	The x-coordinate of the origin.
y	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults to true.

12.19.3.24 void seq64::gui_drawingarea_gtk2::draw_rectangle (Glib::RefPtr< Gdk::Drawable > & *drawable*, int *x*, int *y*, int *lx*, int *ly*, bool *fill* = `true`) [inline], [protected]

Parameters

drawable	The object on which to draw the rectangle.
x	The x-coordinate of the origin.
y	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults to true.

12.19.3.25 void seq64::gui_drawingarea_gtk2::draw_rectangle (Glib::RefPtr< Gdk::Drawable > & *drawable*, const Color & *c*, int *x*, int *y*, int *lx*, int *ly*, bool *fill* = `true`) [protected]

It also supports setting the foreground color to the draw_rectangle() function.

We have a number of such functions: for the main window, for the main pixmap, and for any drawing surface. Is the small bit of conciseness worth it?

Parameters

drawable	The surface on which to draw the box.
c	Provides the foreground color to set.
x	The x-coordinate of the origin.
y	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults to true.

12.19.3.26 void seq64::gui_drawingarea_gtk2::draw_rectangle (Glib::RefPtr< Gdk::Pixmap > & *pixmap*, int *x*, int *y*, int *lx*, int *ly*, bool *fill* = `true`) [inline], [protected]

Parameters

pixmap	The object on which to draw the rectangle.

Parameters

x	The x-coordinate of the origin.
y	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults to true.

12.19.3.27 void seq64::gui_drawingarea_gtk2::draw_rectangle (Glib::RefPtr< Gdk::Pixmap > & *pixmap*, const Color & *c*, int *x*, int *y*, int *lx*, int *ly*, bool *fill* = `true`) [protected]

It also supports setting the foreground color to the draw_rectangle() function.

We have a number of such functions: for the main window, for the main pixmap, and for any drawing surface. Is the small bit of conciseness worth it?

Parameters

pixmap	The surface on which to draw the box.
c	Provides the foreground color to set.
x	The x-coordinate of the origin.
y	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults to true.

12.19.3.28 void seq64::gui_drawingarea_gtk2::draw_rectangle_on_pixmap (int *x*, int *y*, int *lx*, int *ly*, bool *fill* = `true`) [inline], [protected]

Parameters

x	The x-coordinate of the origin.
y	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults to true.

12.19.3.29 void seq64::gui_drawingarea_gtk2::draw_rectangle_on_pixmap (const Color & *c*, int *x*, int *y*, int *lx*, int *ly*, bool *fill* = `true`) [protected]

It adds setting the foreground color to the draw_rectangle() function.

Parameters

c	Provides the foreground color to set.
x	The x-coordinate of the origin.

Parameters

y	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults to true.

12.19.3.30 void seq64::gui_drawingarea_gtk2::draw_normal_rectangle_on_pixmap (int *x*, int *y*, int *lx*, int *ly*, bool *fill* = `true`) [protected]

It uses Gtk to get the proper background styling for the rectange.

Parameters

x	The x-coordinate of the origin.
y	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults to true.

12.19.3.31 void seq64::gui_drawingarea_gtk2::draw_drawable (int *xsrc*, int *ysrc*, int *xdest*, int *ydest*, int *width*, int *height*) [inline], [protected]

12.19.3.32 void seq64::gui_drawingarea_gtk2::scroll_hadjust (Gtk::Adjustment & *hadjust*, double *step*) [protected]

This function is currently duplicated in the gui_drawingarea_gtk2 and gui_window_gtk2 modules.

Parameters

hadjust	Provides a reference to the adjustment object to be adjusted. Do we really need this to be a parameter? Why not just use the m_hadjust member? (Note that this member is not present in the similar gui_window_gtk2 class.)
step	Provides the step value to use for adjusting the horizontal scrollbar. If negative, the adjustment is leftward. If positive, the adjustment is rightward. It can be the value of m_hadjust->get_step_increment(), or provided especially to keep up with the progress bar.

12.19.3.33 void seq64::gui_drawingarea_gtk2::scroll_vadjust (Gtk::Adjustment & *vadjust*, double *step*) [protected]

Parameters

vadjust	Provides a reference to the adjustment object to be adjusted.
step	Provides the step value to use for adjusting the vertical scrollbar. If negative, the adjustment is upward. If positive, the adjustment is downward. It can be the value of m_vadjust->get_step_increment().

12.19.3.34 void seq64::gui_drawingarea_gtk2::scroll_hset (Gtk::Adjustment & *hadjust,* double *value*) [protected]

12.19.3.35 void seq64::gui_drawingarea_gtk2::scroll_vset (Gtk::Adjustment & *vadjust,* double *value*) [protected]

12.19.3.36 void seq64::gui_drawingarea_gtk2::set_current_drop_x (int *x*) [inline], [protected]

Parameters

x	The x value to be set.

12.19.3.37 void seq64::gui_drawingarea_gtk2::set_current_drop_y (int *y*) [inline], [protected]

Parameters

y	The y value to be set.

12.19.3.38 void seq64::gui_drawingarea_gtk2::gtk_drawarea_init ( ) [private]

12.19.3.39 void seq64::gui_drawingarea_gtk2::on_realize ( ) [protected]

It allocates any additional resources that weren't initialized in the constructor.

12.19.4 Field Documentation

12.19.4.1 Glib::RefPtr<Gdk::GC> seq64::gui_drawingarea_gtk2::m_gc [protected]

12.19.4.2 Glib::RefPtr<Gdk::Window> seq64::gui_drawingarea_gtk2::m_window [protected]

Wrapper functions with undecorated wrapper names are used for accessing this item. We hope to be able to hide this items completely some day.

12.19.4.3 Gtk::Adjustment& seq64::gui_drawingarea_gtk2::m_vadjust [protected]

12.19.4.4 Gtk::Adjustment& seq64::gui_drawingarea_gtk2::m_hadjust [protected]

12.19.4.5 Glib::RefPtr<Gdk::Pixmap> seq64::gui_drawingarea_gtk2::m_pixmap [protected]

Wrapper functions with undecorated wrapper names are used for accessing this item. We hope to be able to hide this items completely some day.

12.19.4.6 Glib::RefPtr<Gdk::Pixmap> seq64::gui_drawingarea_gtk2::m_background [protected]

Our wrappers still leave this member exposed (giggle).

12.19.4.7 Glib::RefPtr<Gdk::Pixmap> seq64::gui_drawingarea_gtk2::m_foreground [protected]

Our wrappers still leave this member exposed.

12.19.4.8 perform& seq64::gui_drawingarea_gtk2::m_mainperf [protected]

We could move this into yet another base class, since a number of classes don't need it. Probably not worth the effort at this time.

12.19.4.9 int seq64::gui_drawingarea_gtk2::m_window_x [protected]

Could make this constant, but some windows are resizable.Window width value.

12.19.4.10 int seq64::gui_drawingarea_gtk2::m_window_y [protected]

12.19.4.11 int seq64::gui_drawingarea_gtk2::m_current_x [protected]

Current mouse x value.

12.19.4.12 int seq64::gui_drawingarea_gtk2::m_current_y [protected]

12.19.4.13 int seq64::gui_drawingarea_gtk2::m_drop_x [protected]

Provides the x and y value of where the dragging started.Current mouse x-drop value.

12.19.4.14 int seq64::gui_drawingarea_gtk2::m_drop_y [protected]

12.20 seq64::gui_palette_gtk2 Class Reference

Implements a stock palette of Gdk::Color elements.

Inheritance diagram for seq64::gui_palette_gtk2:



Public Member Functions

- gui_palette_gtk2 ()

  Principal constructor.
- ~gui_palette_gtk2 ()

  Provides a destructor to delete allocated objects.
- const Color & line_color () const

  'Getter' function for member m_line_color Provides an experimental way to change some line colors from black to something else.
- const Color & progress_color () const

  'Getter' function for member m_progress_color Provides an experimental way to change the progress line color from black to something else.
- const Color & black () const

  'Getter' function for member m_black
- const Color & white () const

  'Getter' function for member m_white
- const Color & grey () const

  'Getter' function for member m_grey
- const Color & dark_grey () const

  'Getter' function for member m_dk_grey
- const Color & light_grey () const

  'Getter' function for member m_lt_grey
- const Color & red () const

  'Getter' function for member m_red
- const Color & orange () const

  'Getter' function for member m_orange
- const Color & dark_orange () const

  'Getter' function for member m_dk_orange
- const Color & yellow () const

  'Getter' function for member m_yellow
- const Color & green () const

  'Getter' function for member m_green
- const Color & blue () const

  'Getter' function for member m_blue
- const Color & dark_cyan () const

  'Getter' function for member m_dk_cyan
- const Color & bg_color () const

  'Getter' function for member m_bg_color
- void bg_color (const Color &c)

  'Setter' function for member m_bg_color
- const Color & fg_color () const

  'Getter' function for member m_fg_color
- void fg_color (const Color &c)

  'Setter' function for member m_fg_color

Protected Types

- typedef Gdk::Color Color

  Provides a type for the color object.

Private Attributes

- const Color m_black
  Provides the black color.
- const Color m_white
  Provides the white color.
- const Color m_grey
  Provides the grey color.
- const Color m_dk_grey
  Provides the dark grey color.
- const Color m_lt_grey
  Provides the light grey color.
- const Color m_red
  Provides the red color.
- const Color m_orange
  Provides the orange color.
- const Color m_dk_orange
  Provides a dark orange color.
- const Color m_yellow
  Provides the yellow color.
- const Color m_green
  Provides the green color.
- const Color m_blue
  Provides the blue color.
- const Color m_dk_cyan
  Provides the dark cyan color.
- const Color m_line_color
  Provides the line color.
- const Color m_progress_color
  Provides the progress color.
- Color m_bg_color
  The background color.
- Color m_fg_color
  The foreground color.

12.20.1 Detailed Description

Note that this class must be derived from Gtk::DrawingArea (or Gtk::Widget) in order to get access to the get_↩ default_colormap() function used in the constructor.

12.20.2 Member Typedef Documentation

12.20.2.1 typedef Gdk::Color seq64::gui_palette_gtk2::Color [protected]

The following uses are made of each color:

- Black. The background color of armed patterns. The color of most lines in the user interface, including the main grid lines. The default color of progress lines and text.

- White. The default background color of just about everything drawn in the application.
- Grey. The color of minor grid lines and the markers for the currently-selected scale.
- Dark grey. The color of some grid lines, and the background of a queued pattern slot.
- Light grey. The color of some grid lines.
- Red. The optional color of progress bars.
- Orange. The fill-in color for selected notes and events.
- Dark orange. The color of selected event data lines and the color of the selection box for events to be pasted.
- Yellow. The background of the pattern and name slots for empty patterns. The text color for selected empty pattern slots.
- Green. Not yet used.
- Blue. Not yet used.
- Dark cyan. The background color of muted patterns currently in edit, or the pattern that contains the original data for an imported SMF 0 song. The text color of an unmuted pattern currently in edit. These colors apply to the pattern editor and the song editor. The color of the selected background pattern in the song editor.
- Line color. The generic line color, meant for expansion. Currently black.
- Progress color. The progress line color. Black by default, but can be set to red.
- Background color. The currently-in-use background color. Can vary a lot when a pixmap is being redrawn.
- Foreground color. The currently-in-use foreground color. Can vary a lot when a pixmap is being redrawn.

12.20.3 Constructor & Destructor Documentation

12.20.3.1 seq64::gui_palette_gtk2::gui_palette_gtk2 ( )

In the constructor one can only allocate colors; get_window() returns 0 because this window has not yet been realized. Also note that the possible color names that can be used are found in /usr/share/X11/rgb.txt.

12.20.3.2 seq64::gui_palette_gtk2::~gui_palette_gtk2 ( )

12.20.4 Member Function Documentation

12.20.4.1 const Color& seq64::gui_palette_gtk2::line_color ( ) const [inline]

Might eventually be selectable from the "user" configuration file

12.20.4.2 const Color& seq64::gui_palette_gtk2::progress_color ( ) const [inline]

Might eventually be selectable from the "user" configuration file

12.20.4.3 const Color& seq64::gui_palette_gtk2::black ( ) const [inline]

12.20.4.4 const Color& seq64::gui_palette_gtk2::white ( ) const [inline]

12.20.4.5 const Color& seq64::gui_palette_gtk2::grey ( ) const [inline]

12.20.4.6 const Color& seq64::gui_palette_gtk2::dark_grey ( ) const [inline]

12.20.4.7 const Color& seq64::gui_palette_gtk2::light_grey ( ) const [inline]

12.20.4.8 const Color& seq64::gui_palette_gtk2::red ( ) const [inline]

12.20.4.9 const Color& seq64::gui_palette_gtk2::orange ( ) const [inline]

12.20.4.10 const Color& seq64::gui_palette_gtk2::dark_orange ( ) const [inline]

12.20.4.11 const Color& seq64::gui_palette_gtk2::yellow ( ) const [inline]

12.20.4.12 const Color& seq64::gui_palette_gtk2::green ( ) const [inline]

12.20.4.13 const Color& seq64::gui_palette_gtk2::blue ( ) const [inline]

12.20.4.14 const Color& seq64::gui_palette_gtk2::dark_cyan ( ) const [inline]

12.20.4.15 const Color& seq64::gui_palette_gtk2::bg_color ( ) const [inline]

12.20.4.16 void seq64::gui_palette_gtk2::bg_color (const Color & *c*) [inline]

12.20.4.17 const Color& seq64::gui_palette_gtk2::fg_color ( ) const [inline]

12.20.4.18 void seq64::gui_palette_gtk2::fg_color (const Color & *c*) [inline]

12.20.5 Field Documentation

12.20.5.1 const Color seq64::gui_palette_gtk2::m_black [private]

12.20.5.2 const Color seq64::gui_palette_gtk2::m_white [private]

12.20.5.3 const Color seq64::gui_palette_gtk2::m_grey [private]

12.20.5.4 const Color seq64::gui_palette_gtk2::m_dk_grey [private]

12.20.5.5 const Color seq64::gui_palette_gtk2::m_lt_grey [private]

12.20.5.6 const Color seq64::gui_palette_gtk2::m_red [private]

12.20.5.7 const Color seq64::gui_palette_gtk2::m_orange [private]

12.20.5.8 const Color seq64::gui_palette_gtk2::m_dk_orange [private]

12.20.5.9 const Color seq64::gui_palette_gtk2::m_yellow [private]

12.20.5.10 const Color seq64::gui_palette_gtk2::m_green [private]

12.20.5.11 const Color seq64::gui_palette_gtk2::m_blue [private]

12.20.5.12 const Color seq64::gui_palette_gtk2::m_dk_cyan [private]

12.20.5.13 const Color seq64::gui_palette_gtk2::m_line_color [private]

12.20.5.14 const Color seq64::gui_palette_gtk2::m_progress_color [private]

12.20.5.15 Color seq64::gui_palette_gtk2::m_bg_color [private]

12.20.5.16 Color seq64::gui_palette_gtk2::m_fg_color [private]

12.21 seq64::gui_window_gtk2 Class Reference

This class supports a basic interface for Gtk::Window-derived objects.

Inheritance diagram for seq64::gui_window_gtk2:



Public Member Functions

- gui_window_gtk2 (perform &p, int window_x=0, int window_y=0)

  Principal constructor, has a reference to the all-important perform object.
- virtual ~gui_window_gtk2 ()

  This rote constructor does nothing.

Protected Member Functions

- perform & perf ()

  'Getter' function for member m_mainperf
- virtual void quit ()

  Provides "quit" functionality that WE HAVE OVERLOOKED!!! At some point we need to rectify this situation, probably for the sake of session support.
- int redraw_period_ms () const

  'Getter' function for member m_redraw_period_ms
- bool is_realized () const

'Getter' function for member m_is_realized

- void scroll_hadjust (Gtk::Adjustment &hadjust, double step)

  This function provides optimization for the on_scroll_event() functions, and should provide support for having the seqedit/seqroll/seqtime/seqdata panes follow the scrollbar, in a future upgrade.
- void scroll_vadjust (Gtk::Adjustment &vadjust, double step)

  This function is the vertical version of scroll_hadjust().
- void scroll_hset (Gtk::Adjustment &hadjust, double value)

  This function is the horizontal scroll setter.
- void scroll_vset (Gtk::Adjustment &vadjust, double value)

  This function is the vertical scroll setter.
- void on_realize ()

  This callback function calls the base-class on_realize() function, and sets the m_is_realized flag.

Private Attributes

- perform & m_mainperf

  The master object, sort of a sequence buss for all of the sequence.
- int m_window_x

  Window sizes.
- int m_window_y

  The height of the window.
- int m_redraw_period_ms

  Provides the timer period for the eventedit timer, used to determine the rate of redrawing.
- bool m_is_realized

  Indicates if on_realize() has been called.

12.21.1 Constructor & Destructor Documentation

12.21.1.1 seq64::gui_window_gtk2::gui_window_gtk2 (perform & *p*, int *window_x* = 0, int *window_y* = 0)

Note

We've collected the redraw timeouts into a base-class member. Most were valued at c_redraw_ms (40 ms), but mainwnd used 25 ms, so beware. We will eventually make this a user-interface parameter.

Parameters

p	Refers to the main performance object.
window_x	The width of the window.
window_y	The height of the window.

12.21.1.2 seq64::gui_window_gtk2::~gui_window_gtk2 ( ) [virtual]

12.21.2 Member Function Documentation

12.21.2.1 perform& seq64::gui_window_gtk2::perf ( ) [inline], [protected]

12.21.2.2 virtual void seq64::gui_window_gtk2::quit ( ) [inline], [protected], [virtual]

12.21.2.3 int seq64::gui_window_gtk2::redraw_period_ms ( ) const [inline], [protected]

12.21.2.4 bool seq64::gui_window_gtk2::is_realized ( ) const [inline], [protected]

12.21.2.5 void seq64::gui_window_gtk2::scroll_hadjust (Gtk::Adjustment & *hadjust,* double *step*) [protected]

This function is currently duplicated in the gui_drawingarea_gtk2 and gui_window_gtk2 modules.

Parameters

hadjust	Provides a reference to the adjustment object to be adjusted.
step	Provides the step value to use for adjusting the horizontal scrollbar. If negative, the adjustment is leftward. If positive, the adjustment is rightward. It can be the value of m_hadjust->get_step_increment(), or provided especially to keep up with the progress bar.

12.21.2.6 void seq64::gui_window_gtk2::scroll_vadjust (Gtk::Adjustment & *vadjust,* double *step*) [protected]

Parameters

vadjust	Provides a reference to the adjustment object to be adjusted.
step	Provides the step value to use for adjusting the vertical scrollbar. If greater than 0, the movement is downward. If less than zero, the movement is upward.

12.21.2.7 void seq64::gui_window_gtk2::scroll_hset (Gtk::Adjustment & *hadjust,* double *value*) [protected]

Parameters

hadjust	Provides a reference to the adjustment object to be set. It is clamped as necessary.
value	Provides the value to use for setting the horizontal scrollbar.

12.21.2.8 void seq64::gui_window_gtk2::scroll_vset (Gtk::Adjustment & *vadjust,* double *value*) [protected]

Parameters

hadjust	Provides a reference to the adjustment object to be set. It is clamped as necessary.
value	Provides the value to use for setting the vertical scrollbar.

12.21.2.9 void seq64::gui_window_gtk2::on_realize ( ) [protected]

12.21.3 Field Documentation

12.21.3.1 perform& seq64::gui_window_gtk2::m_mainperf [private]

And a whole lot more than that.

12.21.3.2 int seq64::gui_window_gtk2::m_window_x [private]

Could make this constant, but some windows are resizable.The width of the window.

12.21.3.3 int seq64::gui_window_gtk2::m_window_y [private]

12.21.3.4 int seq64::gui_window_gtk2::m_redraw_period_ms [private]

This is currently hardwired to 40 ms in Linux, and 20 ms in Windows. Note that mainwnd used 25 ms.

12.21.3.5 bool seq64::gui_window_gtk2::m_is_realized [private]

In some cases, we don't want to draw in objects that haven't yet appeared, otherwise crashes occur.

12.22 seq64::jack_assistant Class Reference

This class provides the performance mode JACK support.

Public Member Functions

- jack_assistant (perform &parent, int bpminute=SEQ64_DEFAULT_BPM, int ppqn=SEQ64_USE_DEFAUL↩ T_PPQN, int bpm=SEQ64_DEFAULT_BEATS_PER_MEASURE, int beatwidth=SEQ64_DEFAULT_BEAT↩ _WIDTH)

  This constructor initializes a number of member variables, some of them public!
- ~jack_assistant ()

  The destructor doesn't need to do anything yet.
- perform & parent ()

  'Getter' function for member m_jack_parent Needed for external callbacks.
- bool is_running () const

  'Getter' function for member m_jack_running
- bool is_master () const

  'Getter' function for member m_jack_master
- int get_ppqn () const

  'Getter' function for member m_ppqn
- int get_beat_width () const

  'Getter' function for member m_beat_width
- void set_beat_width (int bw)

  'Setter' function for member m_beat_width
- int get_beats_per_measure () const

  'Getter' function for member m_beats_per_measure
- void set_beats_per_measure (int bpm)

'Setter' function for member m_beats_per_measure

- int get_beats_per_minute () const

  'Getter' function for member m_beats_per_minute
- void set_beats_per_minute (int bpminute)

  'Setter' function for member m_beats_per_minute For the future, changing the BPM (beats/minute) internally.
- bool init ()

  Initializes JACK support.
- bool deinit ()

  Tears down the JACK infrastructure.
- bool session_event ()

  Writes the MIDI file named "<jack session dir>-file.mid" using a midifile object, quits if told to by JACK, and can free the JACK session event.
- void start ()

  If JACK is supported, starts the JACK transport.
- void stop ()

  If JACK is supported, stops the JACK transport.
- void position (bool to_left_tick, bool relocate=false)

  If JACK is supported and running, sets the position of the transport to the new frame number, frame 0.
- bool output (jack_scratchpad &pad)

  Performance output function for JACK, called by the perform function of the same name.
- void set_ppqn (int ppqn)

  'Setter' function for member m_ppqn For the future, changing the PPQN internally.
- double get_jack_tick () const

  'Getter' function for member m_jack_tick
- const jack_position_t & get_jack_pos () const

  'Getter' function for member m_jack_pos

Private Member Functions

- void set_jack_running (bool flag)

  'Setter' function for member m_jack_running
- jack_client_t * client () const

  'Getter' function for member m_jack_client
- const std::string & client_name () const

  'Getter' function for member m_jack_client_name
- const std::string & client_uuid () const

  'Getter' function for member m_jack_client_uuid
- bool info_message (const std::string &msg)

  Common-code for console messages.
- bool error_message (const std::string &msg)

  Common-code for error messages.
- jack_client_t * client_open (const std::string &clientname)

  A more full-featured initialization for a JACK client, which is meant to be called by the init() function.
- void get_jack_client_info ()

  Tries to obtain the best information on the JACK client and the UUID assigned to this client.
- void show_statuses (unsigned bits)

  Loops through the full set of JACK bits, showing the information for any bits that are set in the given parameter.
- void show_position (const jack_position_t &pos) const

  Shows a one-line summary of a JACK position structure.
- int sync (jack_transport_state_t state=(jack_transport_state_t)(-1))

  A helper function for syncing up with JACK parameters.
- void set_position (midipulse currenttick)

  Provides the code that was effectively commented out in the perform::position_jack() function.

Private Attributes

- perform & m_jack_parent

  Provides the perform object that needs this JACK assistant/scratchpad class.

- jack_client_t * m_jack_client

  Provides a handle into JACK, so that the application, as a JACK client, can issue commands and retrieve status information from JACK.

- std::string m_jack_client_name

  A new member to hold the actual name of the client assigned by JACK.

- std::string m_jack_client_uuid

  A new member to hold the actual UUID of the client assigned by JACK.

- jack_nframes_t m_jack_frame_current

  Holds the current frame number obtained from JACK transport, via a call to jack_get_current_transport_frame().

- jack_nframes_t m_jack_frame_last

  Holds the last frame number we got from JACK, so that progress can be tracked.

- jack_position_t m_jack_pos

  Provides positioning information on JACK playback.

- jack_transport_state_t m_jack_transport_state

  Holds the JACK transport state.

- jack_transport_state_t m_jack_transport_state_last

  Holds the last JACK transport state.

- double m_jack_tick

  The tick/pulse value derived from the current frame number, the ticks/beat value, the beats/minute value, and the frame rate.

- jack_session_event_t * m_jsession_ev

  Provides a kind of handle to the JACK session manager.

- bool m_jack_running

  Indicates if JACK Sync has been enabled successfully.

- bool m_jack_master

  Indicates if JACK Sync has been enabled successfully, with the application running as JACK Master.

- int m_ppqn

  Holds the global PPQN value for the Sequencer64 session.

- int m_beats_per_measure

  Holds the song's beats/measure value for using in setting JACK position.

- int m_beat_width

  Holds the song's beat width value (denominator of the time signature) for using in setting JACK position.

- int m_beats_per_minute

  Holds the song's beats/minute (BPM) value for using in setting JACK position.

Static Private Attributes

- static jack_status_pair_t sm_status_pairs [ ]

  Pairs the JACK status bits with human-readable descriptions of each one.

Friends

- int jack_process_callback (jack_nframes_t nframes, void ∗arg)
- void jack_shutdown_callback (void ∗arg)

  This callback is to shutdown JACK by clearing the jack_assistant::m_jack_running flag.
- int jack_sync_callback (jack_transport_state_t state, jack_position_t ∗pos, void ∗arg)

  Global functions for JACK support and JACK sessions.
- void jack_timebase_callback (jack_transport_state_t state, jack_nframes_t nframes, jack_position_t ∗pos, int new_pos, void ∗arg)

  The JACK timebase function defined here sets the JACK position structure.
- void jack_session_callback (jack_session_event_t ∗ev, void ∗arg)

  Set the m_jsession_ev (event) value of the perform object.

12.22.1 Constructor & Destructor Documentation

12.22.1.1 seq64::jack_assistant::jack_assistant (perform & *parent*, int *bpminute* = SEQ64_DEFAULT_BPM, int *ppqn* = SEQ64_USE_DEFAULT_PPQN, int *bpm* = SEQ64_DEFAULT_BEATS_PER_MEASURE, int *beatwidth* = SEQ64_DEFAULT_BEAT_WIDTH)

Note that the perform object currently calls jack_assistant::init(), but that call could be made here instead.

Parameters

parent	Provides a reference to the main perform object that needs to control JACK event.
bpminute	The beats/minute to set up JACK to use (applies to Master setup).
ppqn	The parts-per-quarter-note setting in force for the present tune.
bpm	The beats/measure (time signature numerator) in force for the present tune.
beatwidth	The beat-width (time signature denominator) in force for the present tune.

12.22.1.2 seq64::jack_assistant::∼jack_assistant ( )

The perform object currently calls jack_assistant::deinit(), but that call could be made here instead.

12.22.2 Member Function Documentation

12.22.2.1 perform& seq64::jack_assistant::parent ( ) [inline]

12.22.2.2 bool seq64::jack_assistant::is_running ( ) const [inline]

12.22.2.3 bool seq64::jack_assistant::is_master ( ) const [inline]

12.22.2.4 int seq64::jack_assistant::get_ppqn ( ) const [inline]

12.22.2.5 int seq64::jack_assistant::get_beat_width ( ) const [inline]

12.22.2.6 void seq64::jack_assistant::set_beat_width (int *bw*) [inline]

Parameters

bw	Provides the beat-width (denominator of the time signature) value to set.

12.22.2.7 int seq64::jack_assistant::get_beats_per_measure ( ) const [inline]

12.22.2.8 void seq64::jack_assistant::set_beats_per_measure (int *bpm*) [inline]

Parameters

bpm	Provides the beats/measure (numerator of the time signature) value to set.

12.22.2.9 int seq64::jack_assistant::get_beats_per_minute ( ) const [inline]

12.22.2.10 void seq64::jack_assistant::set_beats_per_minute (int *bpminute*) [inline]

We should consider adding validation. However, perform::set_beats_per_minute() does validate already.

Parameters

bpminute	Provides the beats/minute value to set.

12.22.2.11 bool seq64::jack_assistant::init ( )

Then we become a new client of the JACK server.

A sync callback is needed for polling of slow-sync clients. But seq24/sequencer64 are not slow-sync clients. We don't really need to be a slow-sync client, as far as we can tell. We can't get JACK working exactly the way it does in seq24 without the callback in place. Plus, it does things important to the setup of JACK. So now this setup is permanent.

Jack transport settings:

```
There are three settings:  On, Master, and Master Conditional.
Currently, they can all be selected in the user-interface's File /
Options / JACK/LASH page.  We really want only the proper combinations
to be set, for clarity (the user-interface now takes care of this.  We
need to initialize if any of them are set, and the
rc_settings::with_jack() function tells us that.
```

jack_set_process_callback() patch:

```
Implemented first patch from freddix/seq24 GitHub project, to fix JACK
transport.  One line of code.  Well, we added some error-checking. :-)
Found some old notes on the Web the this patch really only works (to
prevent seq24 freeze) if seq24 is set as JACK Master, or if another
client application, such as Qtractor, is running as JACK Master (and
then seq24 will apparently follow it).
```

Returns

Returns true if JACK is now considered to be running (or if it was already running.)

12.22.2.12 bool seq64::jack_assistant::deinit ( )

Returns

Returns the value of m_jack_running, which should be false.

12.22.2.13 bool seq64::jack_assistant::session_event ( )

ca 2015-07-24 Just a note: The OMA (OpenMandrivaAssociation) patch was already applied to seq24 v.0.9.2. It put quotes around the –file argument. However, the –file option doesn't work, so let's change that line.

```
sequencer64 --file \"${SESSION_DIR}file.mid\" --jack_session_uuid
```

Why are we using a Glib::ustring here? Convenience. But with C++11, we could use a lexical_cast<>. No more ustring, baby! It doesn't really matter; this function can call Gtk::Main::quit(), via the parent's gui().quit() function.

Returns

Always returns false.

12.22.2.14 void seq64::jack_assistant::start ( )

This function assumes that m_jack_client is not null, if m_jack_running is true.

Found this note in the Hydrogen code:

```
When jack_transport_start() is called, it takes effect from the next
processing cycle.  The location info from the timebase_master, if
there is one, will not be available until the _next_ next cycle.  The
code must therefore wait one cycle before syncing up with
timebase_master.
```

12.22.2.15 void seq64::jack_assistant::stop ( )

This function assumes that m_jack_client is not null, if m_jack_running is true.

12.22.2.16 void seq64::jack_assistant::position (bool *to_left_tick*, bool *relocate* = `false`)

This new position takes effect in two process cycles. If there are slow-sync clients and the transport is already rolling, it will enter the JackTransportStarting state and begin invoking their sync_callbacks until ready. This function is realtime-safe.

```
http://jackaudio.org/files/docs/html/transport-design.html
```

This position() function is called via perform::position_jack() in the mainwnd, perfedit, perfroll, and seqroll graphical user-interface support objects.

The code that was disabled sets the current tick to 0 or, if state was true, to the leftmost tick (which is probably the position of the L marker). The current tick is then converted to a frame number, and then we locate the transport to that position. We're going to enable this code, but make it dependent on a new boolean parameter that defaults to false, in anticipation of trying it out later.

These repositions reset the progress bars. We don't always want that, it should be an option. TODO.

jack_transport_reposition():

```
Requests a new transport position.  The new position takes effect in
two process cycles. If there are slow-sync clients and the transport
is already rolling, it will enter the JackTransportStarting state and
begin invoking their sync_callbacks until ready. This function is
realtime-safe.

It's pos parameter provides the requested new transport position. Fill
pos->valid to specify which fields should be taken into account. If
you mark a set of fields as valid, you are expected to fill them all.
Note that "frame" is always assumed, and generally needs to be set:

   http://comments.gmane.org/gmane.comp.audio.jackit/18705

Returns 0 if a valid request, EINVAL if the position structure is
rejected.
```

Warning

A lot of this code is effectively disabled by an early return statement.

Parameters

to_left_tick	If true, the current tick is set to the leftmost tick, instead of the 0th tick. Now used, but only if relocate is true. One question is, do we want to perform this function if rc().with_jack_transport() is true? Seems like we should be able to do it only if m_jack_master is true.
relocate	If true (it defaults to false), then we allow the relocation of the JACK transport to the current_tick or the left tick, rather than to frame 0. EXPERIMENTAL, enables dead code from seq24. Seems to work if set to true when we are the JACK Master. Enabling this code makes "klick -j -P" work, after a fashion. It clicks, but at a way too rapid rate.

12.22.2.17 bool seq64::jack_assistant::output (**jack_scratchpad** & *pad*)

This code comes from perform::output_func() from seq24.

Note

Follow up on this note found "out there": "Maybe I'm wrong but if I understood correctly, recent jack1 transport no longer goes into Jack_Transport_Starting state before going to Jack_Transport_Rolling (this was deliberately dropped), but seq24 currently needs this to start off with jack transport." On the other hand, some people have no issues. This may have been due to the lack of m_jack_pos initialization.

Parameters

pad	Provide a JACK scratchpad for sharing certain items between the perform object and the jack_assistant object.

Returns

Returns true if JACK is running.

12.22.2.18 void seq64::jack_assistant::set_ppqn (int *ppqn*) [inline]

We should consider adding validation. But it is used by perform.

Parameters

ppqn	Provides the PPQN value to set.

12.22.2.19 double seq64::jack_assistant::get_jack_tick ( ) const [inline]

12.22.2.20 const jack_position_t& seq64::jack_assistant::get_jack_pos ( ) const [inline]

12.22.2.21 void seq64::jack_assistant::set_jack_running (bool *flag*) [inline], [private]

Parameters

flag	Provides the is-running value to set.

12.22.2.22 jack_client_t* seq64::jack_assistant::client ( ) const [inline], [private]

12.22.2.23 const std::string& seq64::jack_assistant::client_name ( ) const [inline], [private]

12.22.2.24 const std::string& seq64::jack_assistant::client_uuid ( ) const [inline], [private]

12.22.2.25 bool seq64::jack_assistant::info_message (const std::string & *msg*) [private]

Adds markers and a newline.

Parameters

msg	The message to print, sans the newline.

Returns

Returns true.

12.22.2.26 bool seq64::jack_assistant::error_message (const std::string & *msg*) [private]

Adds markers, and sets m_jack_running to false.

Parameters

msg	The message to print, sans the newline.

Returns

Returns false for convenience/brevity in setting function return values.

12.22.2.27 jack_client_t * seq64::jack_assistant::client_open (const std::string & *clientname*) [private]

Status bits for jack_status_t return pointer:

```
JackNameNotUnique means that the client name was not unique. With
JackUseExactName, this is fatal. Otherwise, the name was modified by
appending a dash and a two-digit number in the range "-01" to "-99".
The jack_get_client_name() function returns the exact string used. If
the specified client_name plus these extra characters would be too
long, the open fails instead.

JackServerStarted means that the JACK server was started as a result
of this operation. Otherwise, it was running already. In either case
the caller is now connected to jackd, so there is no race condition.
When the server shuts down, the client will find out.
```

JackOpenOptions:

```
JackSessionID | JackServerName | JackNoStartServer | JackUseExactName

Only the first is used at present.
```

Parameters

clientname	Provides the name of the client, used in the call to jack_client_open(). By default, this name is the macro SEQ64_PACKAGE (i.e. "sequencer64"). The name scope is local to each server. Unless forbidden by the JackUseExactName option, the server will modify this name to create a unique variant, if needed.

Returns

Returns a pointer to the JACK client if JACK has opened the client connection successfully. Otherwise, a null pointer is returned.

12.22.2.28 void seq64::jack_assistant::get_jack_client_info ( ) [private]

Sets m_jack_client_name and m_jack_client_info as side-effects.

12.22.2.29 void seq64::jack_assistant::show_statuses (unsigned *bits*) [private]

For reference, here are the enumeration values from /usr/include/jack/types.h:

```
        JackFailure         = 0x01
        JackInvalidOption   = 0x02
        JackNameNotUnique   = 0x04
        JackServerStarted   = 0x08
        JackServerFailed    = 0x10
        JackServerError     = 0x20
        JackNoSuchClient    = 0x40
        JackLoadFailure     = 0x80
        JackInitFailure     = 0x100
        JackShmFailure      = 0x200
        JackVersionError    = 0x400
        JackBackendError    = 0x800
        JackClientZombie    = 0x1000
```

Parameters

bits	The mask of the bits to be shown in the output.

12.22.2.30 void seq64::jack_assistant::show_position (const jack_position_t & *pos*) const [private]

This function is meant for experimenting and learning.

The fields of this structure are as follows. Only the fields we care about are shown.

```
    jack_nframes_t      frame_rate:     current frame rate (per second)
    jack_nframes_t      frame:          frame number, always present
    jack_position_bits_t valid:         which other fields are valid


JackPositionBBT:
    int32_t             bar:            current bar
    int32_t             beat:           current beat-within-bar
    int32_t             tick:           current tick-within-beat
    double              bar_start_tick
    float               beats_per_bar:  time signature "numerator"
    float               beat_type:      time signature "denominator"
    double              ticks_per_beat
    double              beats_per_minute


JackBBTFrameOffset:
    jack_nframes_t      bbt_offset;     frame offset for the BBT fields
```

```
Only the most "important" and time-varying fields are shown. The format
output is brief and inscrutable unless you read this format example:


    nnnnn frame B:B:T N/D TPB BPM BBT
      ^     ^     ^   ^ ^  ^   ^   ^
      |     |     |   | |  |   |   |
      |     |     |   | |  |   |    --------- bbt_offset (frame), even if invalid
      |     |     |   | |  |    ------------ beats_per_minute
      |     |     |   | |   ----------------- ticks_per_beat (PPQN * 10?)
      |     |     |   |  -------------------- beat_type (denominator)
      |     |     |    ---------------------- beats_per_bar (numerator)
      |     |      ------------------------- bar : beat : tick
      |      ------------------------------- frame (number)
       ---------------------------------- the "valid" bits


The "valid" field is shown as bits in the same bit order as shown here, but
represented as a five-character string, "nnnnn", n = 0 or 1:


    JackVideoFrameOffset = 0x100
    JackAudioVideoRatio  = 0x080
    JackBBTFrameOffset   = 0x040
    JackPositionTimecode = 0x020
    JackPositionBBT      = 0x010


We care most about nnnnn = "00101" in our experiments (the most common
output will be "00001").  And we don't worry about non-integer
measurements... we truncate them to integers.  Change the output format if
you want to play with non-Western timings.
```

Parameters

pos	The JACK position structure to dump.

12.22.2.31 int seq64::jack_assistant::sync (jack_transport_state_t *state* = (jack_transport_state_t)(-1)) [private]

Sequencer64 is not a slow-sync client, so that callback is not really needed, but we probably need this sub-function here to start out with the right values for interacting with JACK.

Note the call to jack_transport_query(). This call is *not* is seq24, but seems to be needed in sequencer64 because we put m_jack_pos in the initializer list, which sets all its fields to 0. Seq24 accesses m_jack_pos before it ever gets set, but its fields have values. These values are bogus, but are consistent from run to run on my computer, and allow seq24 to follow another JACK Master, on some computers. It explains why people had different experiences with JACK sync.

If we explicity call jack_transport_query() here, without changing the *state* parameter, then sequencer64 also can follow another JACK Master. (CURRENTLY BUGGY!)

Note that we should consider massaging the following jack_position_t members to set them to 0 (or 0.0) if less than 1.0 or 0.5:

- bar_start_tick
- ticks_per_beat
- beats_per_minute
- frame_time
- next_time
- audio_frames_per_video_frame

Also, why does bbt_offset start at 2128362496?

Parameters

state	The JACK transport state to be set.

12.22.2.32 void seq64::jack_assistant::set_position (midipulse *currenttick*) [private]

We might be able to use it in other functions.

Computing the BBT information from the frame number is relatively simple here, but would become complex if we supported tempo or time signature changes at specific locations in the transport timeline.

```
ticks * 10 = jack ticks;
jack ticks / ticks per beat = num beats;
num beats / beats per minute = num minutes
num minutes * 60 = num seconds
num secords * frame_rate  = frame
```

Parameters

currenttick	Provides the current position to be set.

12.22.3 Friends And Related Function Documentation

12.22.3.1 int jack_process_callback (jack_nframes_t *nframes*, void * *arg*) [friend]

12.22.3.2 void jack_shutdown_callback (void * *arg*) [friend]

Parameters

arg	Points to the jack_assistant in charge of JACK support for the perform object.

12.22.3.3 int jack_sync_callback (jack_transport_state_t *state*, jack_position_t * *pos*, void * *arg*) [friend]

This JACK synchronization callback informs the specified perform object of the current state and parameters of JACK.

The transport state will be:

```
-   JackTransportStopped when a new position is requested.
-   JackTransportStarting when the transport is waiting to start.
-   JackTransportRolling when the timeout has expired, and the
    position is now a moving target.
```

Parameters

state	The JACK Transport state.
pos	The JACK position value.
arg	The pointer to the jack_assistant object. Currently not checked for nullity, nor dynamic-casted.

Returns

Returns 1 if the function works, and 0 if something was wrong.

12.22.3.4 void jack_timebase_callback (jack_transport_state_t *state*, jack_nframes_t *nframes*, jack_position_t * *pos*, int *new_pos*, void * *arg*) [friend]

The original version of the function worked properly with Hydrogen, but not with Klick. The new code seems to work with both. More testing and clarification is needed. This new code was "discovered" in the source-code for the "SooperLooper" project:

```
http://essej.net/sooperlooper/
```

The first difference with the new code is that it handles the case where the JACK position is moved (new_pos == true). If this is true, and the JackPositionBBT bit is off in pos->valid, then the new BBT value is set.

The seconds set of differences are in the "else" clause. In the new code, it is very simple: calculate the new tick value, back it off by the number of ticks in a beat, and perhaps go to the first beat of the next bar.

In the old code (complex!), the simple BBT adjustment is always made. This changes (perhaps) the beats_per_bar, beat_type, etc. We need to make these settings use the actual global values for beats set for Sequencer64. Then, if transitioning from JackTransportStarting to JackTransportRolling (instead of checking new_pos!), the BBT values (bar, beat, and tick) are finally adjusted. Here are the steps, with old and new steps noted:

```
-#  Calculate the "delta" ticks based on the current frame, the
    ticks_per_beat, the beats_per_minute, and the frame_rate.  The old
    code saves this in a local, the new code assigns it to pos->tick.
-#  Old code: save this delta as a positive value.
-#  Figure out the settings and modify bar, beat, tick, and
    bar_start_tick.  The old and new code seem to have the same intent,
    but it seems like the new code is faster and also correct.
    -   Old code:  Calculations are made by division and mod
        operations.
    -   New code:  Calculations are made by increments and decrements
        in a while loop.
```

Parameters

state	Indicates the current state of JACK transport.
nframes	The number of JACK frames in the current time period.
pos	Provides the position structure to be filled in, the address of the position structure for the next cycle; pos->frame will be its frame number. If new_pos is FALSE, this structure contains extended position information from the current cycle. If TRUE, it contains whatever was set by the requester. The timebase_callback's task is to update the extended information here.
new_pos	TRUE (non-zero) for a newly requested pos, or for the first cycle after the timebase_callback is defined. This is usually 0 in Sequencer64 at present, and 1 if one, say, presses "rewind" in qjackctl.
arg	Provides the jack_assistant pointer, currently unchecked for nullity.

12.22.3.5 void jack_session_callback (jack_session_event_t * *ev*, void * *arg*) [friend]

Glib is then used to connect in perform::jack_session_event(). However, the perform object's GUI-support interface is used instead of the following, so that the libseq64 library can be independent of a specific GUI framework:

```
Glib::signal_idle().
    connect(sigc::mem_fun(*jack, &jack_assistant::session_event));
```

Parameters

ev	The JACK event to be set.
arg	The pointer to the jack_assistant object. Currently not checked for nullity.

12.22.4 Field Documentation

12.22.4.1 jack_status_pair_t seq64::jack_assistant::sm_status_pairs [static], [private]

Provides a list of JACK status bits, and a brief string to explain the status bit.

Terminated by a 0 value and an empty string.

12.22.4.2 perform& seq64::jack_assistant::m_jack_parent [private]

12.22.4.3 jack_client_t* seq64::jack_assistant::m_jack_client [private]

12.22.4.4 std::string seq64::jack_assistant::m_jack_client_name [private]

We might show this in the user-interface at some point.

12.22.4.5 std::string seq64::jack_assistant::m_jack_client_uuid [private]

We might show this in the user-interface at some point.

12.22.4.6 jack_nframes_t seq64::jack_assistant::m_jack_frame_current [private]

12.22.4.7 jack_nframes_t seq64::jack_assistant::m_jack_frame_last [private]

Also used in incrementing m_jack_tick.

12.22.4.8 jack_position_t seq64::jack_assistant::m_jack_pos [private]

This structure is filled via a call to jack_transport_query(). It holds, among other items, the frame rate (often 48000), the ticks/beat, and the beats/minute.

12.22.4.9 jack_transport_state_t seq64::jack_assistant::m_jack_transport_state [private]

Common values are JackTransportStopped, JackTransportRolling, and JackTransportLooping.

12.22.4.10 jack_transport_state_t seq64::jack_assistant::m_jack_transport_state_last [private]

12.22.4.11 double seq64::jack_assistant::m_jack_tick [private]

12.22.4.12 jack_session_event_t* seq64::jack_assistant::m_jsession_ev [private]

Used in the session_event() function.

12.22.4.13 bool seq64::jack_assistant::m_jack_running [private]

12.22.4.14 bool seq64::jack_assistant::m_jack_master [private]

12.22.4.15 int seq64::jack_assistant::m_ppqn [private]

It is used for calculating ticks/beat (pulses/beat) and for setting the tick position.

12.22.4.16 int seq64::jack_assistant::m_beats_per_measure [private]

12.22.4.17 int seq64::jack_assistant::m_beat_width [private]

12.22.4.18 int seq64::jack_assistant::m_beats_per_minute [private]

12.23 seq64::jack_scratchpad Class Reference

Provide a temporary structure for passing data and results between a perform and jack_assistant object.

Data Fields

- double js_current_tick
  Holds current location.
- double js_total_tick
  Current location ignoring L/R.
- double js_clock_tick
  Identical to js_total_tick.
- bool js_jack_stopped
  Flags perform::inner_stop().
- bool js_dumping
  Non-JACK playback in progress?
- bool js_init_clock
  We now have a good JACK lock.
- bool js_looping
  seqedit loop button is active.
- bool js_playback_mode
  Song mode (versus live mode).
- double js_ticks_converted_last
  Keeps track of position?

12.23.1 Detailed Description

The jack_assistant class already has access to the members of perform, but it needs access to and modification of "local" variables in perform::output_func(). This scratchpad is useful even if JACK support is not enabled.

12.23.2 Field Documentation

12.23.2.1 double seq64::jack_scratchpad::js_current_tick

12.23.2.2 double seq64::jack_scratchpad::js_total_tick

12.23.2.3 double seq64::jack_scratchpad::js_clock_tick

12.23.2.4 bool seq64::jack_scratchpad::js_jack_stopped

12.23.2.5 bool seq64::jack_scratchpad::js_dumping

12.23.2.6 bool seq64::jack_scratchpad::js_init_clock

12.23.2.7 bool seq64::jack_scratchpad::js_looping

12.23.2.8 bool seq64::jack_scratchpad::js_playback_mode

12.23.2.9 double seq64::jack_scratchpad::js_ticks_converted_last

12.24 seq64::jack_status_pair_t Struct Reference

Provides an internal type to make it easier to display a specific and accurate human-readable message when a JACK operation fails.

Data Fields

- unsigned jf_bit

  Holds one of the bit-values from jack_status_t, which is defined as an "enum JackStatus" type.
- std::string jf_meaning

  Holds a textual description of the corresponding status bit.

12.24.1 Field Documentation

12.24.1.1 unsigned seq64::jack_status_pair_t::jf_bit

12.24.1.2 std::string seq64::jack_status_pair_t::jf_meaning

12.25 seq64::keybindentry Class Reference

Class for management of application key-bindings.

Inherits Entry.

Public Member Functions

- keybindentry (type t, unsigned int *location_to_write=nullptr, perform *p=nullptr, long s=0)

  This constructor initializes the member with values dependent on the value type provided in the first parameter.
- void set (unsigned int val)

  Gets the key name from the integer value; if there is one, then it is printed into a temporary buffer, otherwise the value is printed into that buffer as is.
- virtual bool on_key_press_event (GdkEventKey *event)

  Handles a key press by calling set() with the event's key value.

Private Types

Private Attributes

- unsigned int * m_key

  Points to the value of the key that is part of this key-binding.
- type m_type

  Stores the type of key-binding.
- perform * m_perf

  Stores an optional pointer to a perform object.
- long m_slot

  Provides an index into a set of group-keys or event-keys.

Friends

- class options

12.25.1 Member Enumeration Documentation

12.25.1.1 enum seq64::keybindentry::type [private]

Enumerator

location Used for handling a keystroke made while a keyboard-options field is active, for selecting a key via the keyboard, and binding to pattern/sequence boxes, we think. It is used in the options class to associate a key with the binding.

events Used for binding to events.

groups Used for binding to groups.

12.25.2 Constructor & Destructor Documentation

12.25.2.1 seq64::keybindentry::keybindentry (type *t*, unsigned int * *location_to_write* = nullptr, perform * *p* = nullptr, long *s* = 0)

Usage In options, a pointer to a new key-binding entry is managed by calling `keybindentry(keybindentry::location, &perf->keyname)`.

Parameters

t	Provides the type of key-binding: location, events, or groups.
location_to_write	The location that holds the value of the key associated with the key-binding. The default value of this parameter is the null pointer.
p	Points to the performance object used with this key-binding. The default value of this parameter is the null pointer.
s	Provides the slot value for this key-binding. The default value of this parameter is zero.

12.25.3 Member Function Documentation

12.25.3.1 void seq64::keybindentry::set (unsigned int *val*)

Then we call set_text(buf). The set_width_char() function is then called.

12.25.3.2 bool seq64::keybindentry::on_key_press_event (GdkEventKey * *event*) [virtual]

This value is used to set the event or key depending on the value of m_type.

Parameters

event	Provides the key-press event.

Returns

Returns the result of the call to Entry::on_key_press_event().

12.25.4 Friends And Related Function Documentation

12.25.4.1 friend class options [friend]

12.25.5 Field Documentation

12.25.5.1 unsigned int* seq64::keybindentry::m_key [private]

Not yet sure by the address of this key value is needed. It can be a null pointer, as well.

12.25.5.2 type seq64::keybindentry::m_type [private]

12.25.5.3 perform* seq64::keybindentry::m_perf [private]

12.25.5.4 long seq64::keybindentry::m_slot [private]

(This item should be changed to unsigned int, though.)

12.26 seq64::keys_perform Class Reference

This class supports the performance mode.

Inheritance diagram for seq64::keys_perform:



Public Member Functions

- keys_perform ()

This construction initializes a vast number of member variables, some of them public!

- virtual ~keys_perform ()

  The destructor sets some running flags to false, signals this condition, then joins the input and output threads if the were launched.

- void set_keys (const keys_perform_transfer &kpt)

  Copies fields from the transfer structure in this object.

- void get_keys (keys_perform_transfer &kpt)

  Copies fields from this object into the transfer structure.

- unsigned int bpm_up () const

  'Getter' function for member m_key_bpm_up

- void bpm_up (unsigned int x)

  'Setter' function for member m_key_bpm_up

- unsigned int bpm_dn () const

  'Getter' function for member m_key_bpm_dn

- void bpm_dn (unsigned int x)

  'Setter' function for member m_key_bpm_dn

- unsigned int replace () const

  'Getter' function for member m_key_replace

- void replace (unsigned int x)

  'Setter' function for member m_key_replace

- unsigned int queue () const

  'Getter' function for member m_key_queue

- void queue (unsigned int x)

  'Setter' function for member m_key_queue

- unsigned int keep_queue () const

  'Getter' function for member m_key_keep_queue

- void keep_queue (unsigned int x)

  'Setter' function for member m_key_keep_queue

- unsigned int snapshot_1 () const

  'Getter' function for member m_key_snapshot_1

- void snapshot_1 (unsigned int x)

  'Setter' function for member m_key_snapshot_1

- unsigned int snapshot_2 () const

  'Getter' function for member m_key_snapshot_2

- void snapshot_2 (unsigned int x)

  'Setter' function for member m_key_snapshot_2

- unsigned int screenset_up () const

  'Getter' function for member m_key_screenset_up

- void screenset_up (unsigned int x)

  'Setter' function for member m_key_screenset_up

- unsigned int screenset_dn () const

  'Getter' function for member m_key_screenset_dn

- void screenset_dn (unsigned int x)

  'Setter' function for member m_key_screenset_dn

- unsigned int set_playing_screenset () const

  'Getter' function for member m_key_playing_screenset

- void set_playing_screenset (unsigned int x)

  'Setter' function for member m_key_playing_screenset

- unsigned int group_on () const

  'Getter' function for member m_key_group_on

- void group_on (unsigned int x)

'Setter' function for member m_key_group_on

- unsigned int group_off () const

  'Getter' function for member m_key_group_off

- void group_off (unsigned int x)

  'Setter' function for member m_key_group_off

- unsigned int group_learn () const

  'Getter' function for member m_key_group_learn

- void group_learn (unsigned int x)

  'Setter' function for member m_key_group_learn

- unsigned int start () const

  'Getter' function for member m_key_start

- void start (unsigned int x)

  'Setter' function for member m_key_start

- unsigned int pause () const

  'Getter' function for member m_key_pause

- void pause (unsigned int x)

  'Setter' function for member m_key_pause

- unsigned int pattern_edit () const

  'Getter' function for member m_key_pattern_edit

- void pattern_edit (unsigned int x)

  'Setter' function for member m_key_pattern_edit

- unsigned int event_edit () const

  'Getter' function for member m_key_event_edit

- void event_edit (unsigned int x)

  'Setter' function for member m_key_event_edit

- unsigned int stop () const

  'Getter' function for member m_key_stop

- void stop (unsigned int x)

  'Setter' function for member m_key_stop

- bool show_ui_sequence_key () const

  'Getter' function for member m_key_show_ui_sequency_key

- void show_ui_sequence_key (bool flag)

  'Setter' function for member m_key_show_ui_sequency_key

- bool show_ui_sequence_number () const

  'Getter' function for member m_key_show_ui_sequency_number

- void show_ui_sequence_number (bool flag)

  'Setter' function for member m_key_show_ui_sequency_key

- SlotMap & get_key_events ()

  'Getter' function for member m_key_events

- SlotMap & get_key_groups ()

  'Getter' function for member m_key_groups

- RevSlotMap & get_key_events_rev ()

  'Getter' function for member m_key_events_rev

- RevSlotMap & get_key_groups_rev ()

  'Getter' function for member m_key_groups_rev

- unsigned int lookup_keyevent_key (long seqnum)

  'Getter' function for member m_key_events_rev[seqnum];

- long lookup_keyevent_seq (unsigned int keycode)

  'Getter' function for member m_key_events_rev[keycode];

- unsigned int lookup_keygroup_key (long groupnum)

  'Getter' function for member m_key_events_rev[groupnum];

- long lookup_keygroup_group (unsigned int keycode)

  'Getter' function for member m_key_events_rev[keycode];
- virtual std::string key_name (unsigned int key) const

  Obtains the name of the key.
- virtual void set_all_key_events ()

  Provides base class functionality.
- virtual void set_all_key_groups ()

  Provides base class functionality.
- void set_key_event (unsigned int keycode, long sequence_slot)

  At construction time, this function sets up one keycode and one event slot.
- void set_key_group (unsigned int keycode, long group_slot)

  At construction time, this function sets up one keycode and one group slot.

Protected Types

- typedef std::map< unsigned int, long > SlotMap

  This typedef defines a map in which the key is the keycode, that is, the integer value of a keystroke, and the value is the pattern/sequence number or slot.
- typedef std::map< long, unsigned int > RevSlotMap

  This typedef is like SlotMap, but used for lookup in the other direction.

Protected Member Functions

- unsigned int * at_bpm_up ()

  The following are tricky ways to get at address of the key and group operation values so that we don't directly expose the members to manipulation.
- unsigned int * at_bpm_dn ()

  'Getter' function for member m_key_bpm_dn
- unsigned int * at_replace ()

  'Getter' function for member m_key_replace
- unsigned int * at_queue ()

  'Getter' function for member m_key_queue
- unsigned int * at_keep_queue ()

  'Getter' function for member m_key_keep_queue
- unsigned int * at_snapshot_1 ()

  'Getter' function for member m_key_snapshot_1
- unsigned int * at_snapshot_2 ()

  'Getter' function for member m_key_snapshot_2
- unsigned int * at_screenset_up ()

  'Getter' function for member m_key_screenset_up
- unsigned int * at_screenset_dn ()

  'Getter' function for member m_key_screenset_dn
- unsigned int * at_set_playing_screenset ()

  'Getter' function for member m_key_playing_screenset
- unsigned int * at_group_on ()

  'Getter' function for member m_key_group_on
- unsigned int * at_group_off ()

  'Getter' function for member m_key_group_off
- unsigned int * at_group_learn ()

  'Getter' function for member m_key_group_learn

- unsigned int * at_start ()

  'Getter' function for member m_key_start
- unsigned int * at_pause ()

  'Getter' function for member m_key_pause
- unsigned int * at_pattern_edit ()

  'Getter' function for member m_key_pattern_edit
- unsigned int * at_event_edit ()

  'Getter' function for member m_key_event_edit
- unsigned int * at_stop ()

  'Getter' function for member m_key_stop
- bool * at_show_ui_sequence_key ()

  'Getter' function for member m_key_show_ui_sequence_key
- bool * at_show_ui_sequence_number ()

  'Getter' function for member m_key_show_ui_sequence_number

Private Attributes

- bool m_key_show_ui_sequence_key

  If set, shows the shortcut-keys on each filled pattern slot in the main window.
- bool m_key_show_ui_sequence_number

  If set, shows the sequence number on each filled pattern and empty pattern slot in the main window.
- SlotMap m_key_events

  Holds the mapping of keys to the pattern slots.
- SlotMap m_key_groups

  Holds the mapping of keys to the mute groups.
- RevSlotMap m_key_events_rev

  Holds the reverse mapping of the pattern slots to the keys.
- RevSlotMap m_key_groups_rev

  Holds the reverse mapping of the mute groups to the keys.
- unsigned int m_key_bpm_up

  Provides key assignments for some key sequencer features.
- unsigned int m_key_bpm_dn

  BPM down, semicolon.
- unsigned int m_key_replace

  Replace, Ctrl-L.
- unsigned int m_key_queue

  Queue, Ctrl-R.
- unsigned int m_key_keep_queue

  Keep queue, backslash.
- unsigned int m_key_snapshot_1

  Snapshot 1, Alt-L.
- unsigned int m_key_snapshot_2

  Snapshot 1, Alt-R.
- unsigned int m_key_screenset_up

  Set up, Right-].
- unsigned int m_key_screenset_dn

  Set down, Left-[.
- unsigned int m_key_set_playing_screenset

  Set set, Home key.
- unsigned int m_key_group_on

Group on, igrave key.

- unsigned int m_key_group_off

  Group off, apostrophe!

- unsigned int m_key_group_learn

  Group learn, Insert.

- unsigned int m_key_start

  Start play, Space key.

- unsigned int m_key_pause

  Pause play, Period.

- unsigned int m_key_pattern_edit

  Show pattern editor.

- unsigned int m_key_event_edit

  Show event editor.

- unsigned int m_key_stop

  Stop play, Escape.

Friends

- class options
- class perform
- class optionsfile

12.26.1 Detailed Description

It provides a way a mapping keystrokes to sequencer actions and song settings.

12.26.2 Member Typedef Documentation

12.26.2.1 typedef std::map<unsigned int, long> seq64::keys_perform::SlotMap [protected]

12.26.2.2 typedef std::map<long, unsigned int> seq64::keys_perform::RevSlotMap [protected]

12.26.3 Constructor & Destructor Documentation

12.26.3.1 seq64::keys_perform::keys_perform ( )

12.26.3.2 seq64::keys_perform::~keys_perform ( ) [virtual]

Finally, any active patterns/sequences are deleted.

12.26.4 Member Function Documentation

12.26.4.1 void seq64::keys_perform::set_keys (const keys_perform_transfer & *kpt*)

This structure holds all of the key settings from the File / Options / Keyboard tab dialog.

Parameters

kpt	The structure that holds the values of the keys to be used for various purposes in controlling a performance live.

12.26.4.2 void seq64::keys_perform::get_keys (keys_perform_transfer & *kpt*)

Parameters

kpt	The structure that holds the values of the keys to be used for various purposes in controlling a performance live.

12.26.4.3 unsigned int seq64::keys_perform::bpm_up ( ) const [inline]

12.26.4.4 void seq64::keys_perform::bpm_up (unsigned int *x*) [inline]

Parameters

x	The key value to assign to the operation.

12.26.4.5 unsigned int seq64::keys_perform::bpm_dn ( ) const [inline]

12.26.4.6 void seq64::keys_perform::bpm_dn (unsigned int *x*) [inline]

Parameters

x	The key value to assign to the operation.

12.26.4.7 unsigned int seq64::keys_perform::replace ( ) const [inline]

12.26.4.8 void seq64::keys_perform::replace (unsigned int *x*) [inline]

Parameters

x	The key value to assign to the operation.

12.26.4.9 unsigned int seq64::keys_perform::queue ( ) const [inline]

12.26.4.10 void seq64::keys_perform::queue (unsigned int *x*) [inline]

Parameters

x	The key value to assign to the operation.

12.26.4.11 unsigned int seq64::keys_perform::keep_queue ( ) const [inline]

12.26.4.12 void seq64::keys_perform::keep_queue (unsigned int *x*) [inline]

Parameters

x	The key value to assign to the operation.

12.26.4.13 unsigned int seq64::keys_perform::snapshot_1 ( ) const [inline]

12.26.4.14 void seq64::keys_perform::snapshot_1 (unsigned int *x*) [inline]

Parameters

x	The key value to assign to the operation.

12.26.4.15 unsigned int seq64::keys_perform::snapshot_2 ( ) const [inline]

12.26.4.16 void seq64::keys_perform::snapshot_2 (unsigned int *x*) [inline]

Parameters

x	The key value to assign to the operation.

12.26.4.17 unsigned int seq64::keys_perform::screenset_up ( ) const [inline]

12.26.4.18 void seq64::keys_perform::screenset_up (unsigned int *x*) [inline]

Parameters

x	The key value to assign to the operation.

12.26.4.19 unsigned int seq64::keys_perform::screenset_dn ( ) const [inline]

12.26.4.20 void seq64::keys_perform::screenset_dn (unsigned int *x*) [inline]

Parameters

x	The key value to assign to the operation.

12.26.4.21 unsigned int seq64::keys_perform::set_playing_screenset ( ) const [inline]

12.26.4.22 void seq64::keys_perform::set_playing_screenset (unsigned int *x*) [inline]

Parameters

x	The key value to assign to the operation.

12.26.4.23 unsigned int seq64::keys_perform::group_on ( ) const [inline]

12.26.4.24 void seq64::keys_perform::group_on (unsigned int *x*) [inline]

Parameters

x	The key value to assign to the operation.

12.26.4.25 unsigned int seq64::keys_perform::group_off ( ) const [inline]

12.26.4.26 void seq64::keys_perform::group_off (unsigned int *x*) [inline]

Parameters

x	The key value to assign to the operation.

12.26.4.27 unsigned int seq64::keys_perform::group_learn ( ) const [inline]

12.26.4.28 void seq64::keys_perform::group_learn (unsigned int *x*) [inline]

Parameters

x	The key value to assign to the operation.

12.26.4.29 unsigned int seq64::keys_perform::start ( ) const [inline]

12.26.4.30 void seq64::keys_perform::start (unsigned int *x*) [inline]

Parameters

x	The key value to assign to the operation.

12.26.4.31 unsigned int seq64::keys_perform::pause ( ) const [inline]

12.26.4.32 void seq64::keys_perform::pause (unsigned int *x*) [inline]

Parameters

x	The key value to assign to the operation.

12.26.4.33 unsigned int seq64::keys_perform::pattern_edit ( ) const [inline]

12.26.4.34 void seq64::keys_perform::pattern_edit (unsigned int *x*) [inline]

Parameters

x	The key value to assign to the operation.

12.26.4.35 unsigned int seq64::keys_perform::event_edit ( ) const [inline]

12.26.4.36 void seq64::keys_perform::event_edit (unsigned int *x*) [inline]

Parameters

x	The key value to assign to the operation.

12.26.4.37 unsigned int seq64::keys_perform::stop ( ) const [inline]

12.26.4.38 void seq64::keys_perform::stop (unsigned int *x*) [inline]

Parameters

x	The key value to assign to the operation.

12.26.4.39 bool seq64::keys_perform::show_ui_sequence_key ( ) const [inline]

Used in mainwid, options, optionsfile, userfile, and perform.

12.26.4.40 void seq64::keys_perform::show_ui_sequence_key (bool *flag*) [inline]

Parameters

flag	The flag for showing the sequence key characters in each pattern slot.

12.26.4.41 bool seq64::keys_perform::show_ui_sequence_number ( ) const [inline]

Used in mainwid, options, optionsfile, userfile, and perform.

12.26.4.42 void seq64::keys_perform::show_ui_sequence_number (bool *flag*) [inline]

Parameters

flag	The flag for showing the sequence number in each pattern slot.

12.26.4.43 SlotMap& seq64::keys_perform::get_key_events ( ) [inline]

12.26.4.44 SlotMap& seq64::keys_perform::get_key_groups ( ) [inline]

12.26.4.45 RevSlotMap& seq64::keys_perform::get_key_events_rev ( ) [inline]

12.26.4.46 RevSlotMap& seq64::keys_perform::get_key_groups_rev ( ) [inline]

12.26.4.47 unsigned int seq64::keys_perform::lookup_keyevent_key (long *seqnum*) [inline]

Parameters

seqnum	Provides the sequence number to look up in the reverse key map for patterns/sequences. If the count for this value is 0, then a question mark character is returned. Not checked for maximum!

12.26.4.48 long seq64::keys_perform::lookup_keyevent_seq (unsigned int *keycode*) [inline]

Parameters

keycode	Provides the keycode to look up in the (forward) key map for patterns/sequences. If the count for this value is 0, then a 0 is returned.

12.26.4.49 unsigned int seq64::keys_perform::lookup_keygroup_key (long *groupnum*) [inline]

Parameters

groupnum	Provides the group number to look up in the reverse key map for groups. If the count for this value is 0, then a question mark character is returned.

12.26.4.50 long seq64::keys_perform::lookup_keygroup_group (unsigned int *keycode*) [inline]

Parameters

keycode	Provides the sequence number to look up in the reverse key map for groups. If the count for this value is 0, then a 0 is returned.

12.26.4.51 std::string seq64::keys_perform::key_name (unsigned int *key*) const [virtual]

In gtkmm, this is done via the gdk_keyval_name() function. Here, in the base class, we just provide an easy-to-create string.

Parameters

key	Provides the numeric value of the keystroke.

Returns

Returns the name of the key, in the format "Key 0xkkkk".

Reimplemented in seq64::keys_perform_gtk2.

12.26.4.52 virtual void seq64::keys_perform::set_all_key_events ( ) [inline], [virtual]

Must be called by the derived-class's override of this function.

Reimplemented in seq64::keys_perform_gtk2.

12.26.4.53 virtual void seq64::keys_perform::set_all_key_groups ( ) [inline], [virtual]

Must be called by the derived-class's override of this function.

Reimplemented in seq64::keys_perform_gtk2.

12.26.4.54 void seq64::keys_perform::set_key_event (unsigned int *keycode,* long *sequence_slot*)

It is called 32 times, corresponding the pattern/sequence slots in the Patterns window.

Parameters

keycode	The key to be assigned.
sequence_slot	The perform event slot into which the keycode will be assigned.

12.26.4.55 void seq64::keys_perform::set_key_group (unsigned int *keycode,* long *group_slot*)

It is called 32 times, corresponding the pattern/sequence slots in the Patterns window.

Parameters

keycode	The key to be assigned.
group_slot	The perform group slot into which the keycode will be assigned.

12.26.4.56 unsigned int* seq64::keys_perform::at_bpm_up ( ) [inline], [protected]

They are used in the options module, and, for brevity, are accessed using the PREFKEY_ADDR() macro. *'Getter' function* for member *m_key_bpm_up*

Address getter for the bpm_up operation.

12.26.4.57 unsigned int* seq64::keys_perform::at_bpm_dn ( ) [inline], [protected]

Address getter for the bpm_dn operation.

12.26.4.58 unsigned int* seq64::keys_perform::at_replace ( ) [inline], [protected]

Address getter for the replace operation.

12.26.4.59 unsigned int* seq64::keys_perform::at_queue ( ) [inline], [protected]

Address getter for the queue operation.

12.26.4.60 unsigned int* seq64::keys_perform::at_keep_queue ( ) [inline], [protected]

Address getter for the keep_queue operation.

12.26.4.61 unsigned int* seq64::keys_perform::at_snapshot_1 ( ) [inline], [protected]

Address getter for the snapshot_1 operation.

12.26.4.62 unsigned int* seq64::keys_perform::at_snapshot_2 ( ) [inline], [protected]

Address getter for the snapshot_2 operation.

12.26.4.63 unsigned int* seq64::keys_perform::at_screenset_up ( ) [inline], [protected]

Address getter for the screenset_up operation.

12.26.4.64 unsigned int* seq64::keys_perform::at_screenset_dn ( ) [inline], [protected]

Address getter for the screenset_dn operation.

12.26.4.65 unsigned int* seq64::keys_perform::at_set_playing_screenset ( ) [inline], [protected]

Address getter for the set_playing_screenset operation.

12.26.4.66 unsigned int* seq64::keys_perform::at_group_on ( ) [inline], [protected]

Address getter for the group_on operation.

12.26.4.67 unsigned int* seq64::keys_perform::at_group_off ( ) [inline], [protected]

Address getter for the group_off operation.

12.26.4.68 unsigned int* seq64::keys_perform::at_group_learn ( ) [inline], [protected]

Address getter for the group_learn operation.

12.26.4.69 unsigned int* seq64::keys_perform::at_start ( ) [inline], [protected]

Address getter for the start operation.

12.26.4.70 unsigned int* seq64::keys_perform::at_pause ( ) [inline], [protected]

Address getter for the pause operation.

12.26.4.71 unsigned int* seq64::keys_perform::at_pattern_edit ( ) [inline], [protected]

Address getter for the pattern edit operation.

12.26.4.72 unsigned int* seq64::keys_perform::at_event_edit ( ) [inline], [protected]

Address getter for the event edit operation.

12.26.4.73 unsigned int* seq64::keys_perform::at_stop ( ) [inline], [protected]

Address getter for the stop operation.

12.26.4.74 bool* seq64::keys_perform::at_show_ui_sequence_key ( ) [inline], [protected]

Address getter for the show_ui_sequence_key value.

12.26.4.75 bool* seq64::keys_perform::at_show_ui_sequence_number ( ) [inline], [protected]

Address getter for the show_ui_sequence_number value.

12.26.5 Friends And Related Function Documentation

12.26.5.1 friend class options [friend]

12.26.5.2 friend class perform [friend]

12.26.5.3 friend class optionsfile [friend]

12.26.6 Field Documentation

12.26.6.1 bool seq64::keys_perform::m_key_show_ui_sequence_key [private]

12.26.6.2 bool seq64::keys_perform::m_key_show_ui_sequence_number [private]

Also shows the sequence number as part of the sequence name in the performance window (song editor). Always disabled in legacy mode.

12.26.6.3 SlotMap seq64::keys_perform::m_key_events [private]

Do not access directly, use the set/lookup functions declared below.

12.26.6.4 SlotMap seq64::keys_perform::m_key_groups [private]

Do not access directly, use the set/lookup functions declared below.

12.26.6.5 RevSlotMap seq64::keys_perform::m_key_events_rev [private]

Do not access directly, use the set/lookup functions declared below.

12.26.6.6 RevSlotMap seq64::keys_perform::m_key_groups_rev [private]

Do not access directly, use the set/lookup functions declared below.

12.26.6.7 unsigned int seq64::keys_perform::m_key_bpm_up [private]

Used in mainwnd, options, optionsfile, perfedit, seqroll, userfile, and perform.

We could instead use the keys_perform_transfer structure instead of all these individual members.BPM up, apostrophe!!!

12.26.6.8 unsigned int seq64::keys_perform::m_key_bpm_dn [private]

12.26.6.9 unsigned int seq64::keys_perform::m_key_replace [private]

12.26.6.10 unsigned int seq64::keys_perform::m_key_queue [private]

12.26.6.11 unsigned int seq64::keys_perform::m_key_keep_queue [private]

12.26.6.12 unsigned int seq64::keys_perform::m_key_snapshot_1 [private]

12.26.6.13 unsigned int seq64::keys_perform::m_key_snapshot_2 [private]

12.26.6.14 unsigned int seq64::keys_perform::m_key_screenset_up [private]

12.26.6.15 unsigned int seq64::keys_perform::m_key_screenset_dn [private]

12.26.6.16 unsigned int seq64::keys_perform::m_key_set_playing_screenset [private]

12.26.6.17 unsigned int seq64::keys_perform::m_key_group_on [private]

12.26.6.18 unsigned int seq64::keys_perform::m_key_group_off [private]

12.26.6.19 unsigned int seq64::keys_perform::m_key_group_learn [private]

12.26.6.20 unsigned int seq64::keys_perform::m_key_start [private]

12.26.6.21 unsigned int seq64::keys_perform::m_key_pause [private]

12.26.6.22 unsigned int seq64::keys_perform::m_key_pattern_edit [private]

12.26.6.23 unsigned int seq64::keys_perform::m_key_event_edit [private]

12.26.6.24 unsigned int seq64::keys_perform::m_key_stop [private]

12.27 seq64::keys_perform_gtk2 Class Reference

This class supports the performance mode.

Inheritance diagram for seq64::keys_perform_gtk2:



Public Member Functions

- keys_perform_gtk2 ()

  This construction initializes a vast number of member variables, some of them public!
- virtual ~keys_perform_gtk2 ()

  A rote virtual destructor.
- virtual std::string key_name (unsigned int key) const

- virtual void set_all_key_events ()

  Sets up the keys for arming/unmuting events in the Gtk-2 environment.
- virtual void set_all_key_groups ()

  Sets up the keys for group events in the Gtk-2 environment.

Additional Inherited Members

12.27.1 Detailed Description

It has way too many data members, many of the public. Might be ripe for refactoring.

12.27.2 Constructor & Destructor Documentation

12.27.2.1 seq64::keys_perform_gtk2::keys_perform_gtk2 ( )

12.27.2.2 seq64::keys_perform_gtk2::~keys_perform_gtk2 ( ) [virtual]

No action.

12.27.3 Member Function Documentation

12.27.3.1 virtual std::string seq64::keys_perform_gtk2::key_name (unsigned int *key*) const [inline], [virtual]

Reimplemented from seq64::keys_perform.

12.27.3.2 void seq64::keys_perform_gtk2::set_all_key_events ( ) [virtual]

The base-class function call makes sure the the related lists are cleared before rebuilding them here.

Reimplemented from seq64::keys_perform.

12.27.3.3 void seq64::keys_perform_gtk2::set_all_key_groups ( ) [virtual]

The base-class function call makes sure the the related lists are cleared before rebuilding them here.

Reimplemented from seq64::keys_perform.

12.28 seq64::keys_perform_transfer Struct Reference

Provides a data-transfer structure to make it easier to fill in a keys_perform object's members using sscanf().

Data Fields

- unsigned int kpt_bpm_up
- unsigned int kpt_bpm_dn
- unsigned int kpt_screenset_up
- unsigned int kpt_screenset_dn
- unsigned int kpt_set_playing_screenset
- unsigned int kpt_group_on
- unsigned int kpt_group_off
- unsigned int kpt_group_learn
- unsigned int kpt_replace
- unsigned int kpt_queue
- unsigned int kpt_keep_queue
- unsigned int kpt_snapshot_1
- unsigned int kpt_snapshot_2
- unsigned int kpt_start
- unsigned int kpt_stop
- bool kpt_show_ui_sequence_key
- bool kpt_show_ui_sequence_number
- unsigned int kpt_pattern_edit
- unsigned int kpt_event_edit
- unsigned int kpt_pause

12.28.1 Field Documentation

12.28.1.1 unsigned int seq64::keys_perform_transfer::kpt_bpm_up

12.28.1.2 unsigned int seq64::keys_perform_transfer::kpt_bpm_dn

12.28.1.3 unsigned int seq64::keys_perform_transfer::kpt_screenset_up

12.28.1.4 unsigned int seq64::keys_perform_transfer::kpt_screenset_dn

12.28.1.5 unsigned int seq64::keys_perform_transfer::kpt_set_playing_screenset

12.28.1.6 unsigned int seq64::keys_perform_transfer::kpt_group_on

12.28.1.7 unsigned int seq64::keys_perform_transfer::kpt_group_off

12.28.1.8 unsigned int seq64::keys_perform_transfer::kpt_group_learn

12.28.1.9 unsigned int seq64::keys_perform_transfer::kpt_replace

12.28.1.10 unsigned int seq64::keys_perform_transfer::kpt_queue

12.28.1.11 unsigned int seq64::keys_perform_transfer::kpt_keep_queue

12.28.1.12 unsigned int seq64::keys_perform_transfer::kpt_snapshot_1

12.28.1.13 unsigned int seq64::keys_perform_transfer::kpt_snapshot_2

12.28.1.14 unsigned int seq64::keys_perform_transfer::kpt_start

12.28.1.15 unsigned int seq64::keys_perform_transfer::kpt_stop

12.28.1.16 bool seq64::keys_perform_transfer::kpt_show_ui_sequence_key

12.28.1.17 bool seq64::keys_perform_transfer::kpt_show_ui_sequence_number

12.28.1.18 unsigned int seq64::keys_perform_transfer::kpt_pattern_edit

12.28.1.19 unsigned int seq64::keys_perform_transfer::kpt_event_edit

12.28.1.20 unsigned int seq64::keys_perform_transfer::kpt_pause

12.29 seq64::keystroke Class Reference

Encapsulates any practical keystroke.

Public Member Functions

- keystroke ()

  The default constructor for class keystroke.
- keystroke (unsigned int key, bool press=SEQ64_KEYSTROKE_PRESS, int modkey=int(SEQ64_NO_MA↩SK))

  The principal constructor.
- keystroke (const keystroke &rhs)

  Provides the rote copy constructor.
- keystroke & operator= (const keystroke &rhs)

  Provides the rote principal assignment operator.
- bool is_press () const

  'Getter' function for member m_is_press
- bool is_letter (unsigned int ch=SEQ64_KEYSTROKE_BAD_VALUE) const

  'Getter' function for member m_key to test letters, handles ASCII only.
- bool is (unsigned int ch)

  Tests the key value to see if it matches the given character exactly (no case-insensitivity).
- bool is_delete () const

  'Getter' function for member m_key to test for a delete-causing key.
- unsigned int key () const

  'Getter' function for member m_key
- void shift_lock ()

  If a lower-case letter, a number, or another character on the "main" part of the keyboard, shift the m_key value to upper-case or the character shifted on a standard American keyboard.
- seq_modifier_t modifier () const

  'Getter' function for member m_modifier
- bool mod_control () const

  'Getter' function for member m_modifier tested for Ctrl key.
- bool mod_control_shift () const

  'Getter' function for member m_modifier tested for Ctrl and Shift key.
- bool mod_super () const

  'Getter' function for member m_modifier tested for Mod4/Super/Windows key.

Private Attributes

- bool m_is_press

  Determines if the key was a press or a release.
- unsigned int m_key

  The key that was pressed or released.
- seq_modifier_t m_modifier

  The optional modifier value.

12.29.1 Detailed Description

Useful in passing more generic events to non-GUI classes.

12.29.2 Constructor & Destructor Documentation

12.29.2.1 seq64::keystroke::keystroke ( )

12.29.2.2 seq64::keystroke::keystroke (unsigned int *key*, bool *press* = SEQ64_KEYSTROKE_PRESS, int *modkey* = int(**SEQ64_NO_MASK**))

Parameters

key	The keystroke number of the key that was pressed or released.
press	If true, the keystroke action was a press, otherwise it was a release.
modkey	The modifier key combination that was pressed, if any, in the form of a bit-mask, as defined in the gdk_basic_keys module. Common mask values are SEQ64_SHIFT_MASK, SEQ64_CONTROL_MASK, SEQ64_MOD1_MASK, and SEQ64_MOD4_MASK. If no modifier, this value is SEQ64_NO_MASK.

12.29.2.3 seq64::keystroke::keystroke (const **keystroke** & *rhs*)

Parameters

rhs	The object to be copied.

12.29.3 Member Function Documentation

12.29.3.1 **keystroke** & seq64::keystroke::operator= (const **keystroke** & *rhs*)

Parameters

rhs	The object to be assigned.

Returns

Returns the reference to the current object, for use in assignment chains.

12.29.3.2 bool seq64::keystroke::is_press ( ) const [inline]

12.29.3.3 bool seq64::keystroke::is_letter (unsigned int *ch* = SEQ64_KEYSTROKE_BAD_VALUE) const

Parameters

ch	An optional character to test as an ASCII letter.

Returns

If a character is not provided, true is returned if it is an upper or lower-case letter. Otherwise, true is returned if the m_key value matches the character case-insensitively.

Tricky Code

12.29.3.4 bool seq64::keystroke::is (unsigned int *ch*) [inline]

Parameters

ch	The character to be tested.

Returns

Returns true if m_key == ch.

12.29.3.5 bool seq64::keystroke::is_delete ( ) const [inline]

12.29.3.6 unsigned int seq64::keystroke::key ( ) const [inline]

12.29.3.7 void seq64::keystroke::shift_lock ( )

Currently also assumes the ASCII character set.

There's an oddity here: the shift of '2' is the '@' character, but seq24 seems to have treated it like the "" character. Some others were treated the same:

```
Key:        1 2 3 4 5 6 7 8 9 0
Shift:      ! @ # $ % ^ & * ( )
Seq24:      ! " # $ % & ' ( ) space
```

```
This function is meant to avoid using the Caps-Lock when picking a
group-learn character in the group-learn mode.
```

12.29.3.8 seq_modifier_t seq64::keystroke::modifier ( ) const [inline]

12.29.3.9 bool seq64::keystroke::mod_control ( ) const [inline]

12.29.3.10 bool seq64::keystroke::mod_control_shift ( ) const [inline]

12.29.3.11 bool seq64::keystroke::mod_super ( ) const [inline]

12.29.4 Field Documentation

12.29.4.1 bool seq64::keystroke::m_is_press [private]

See the SEQ64_KEYSTROKE_PRESS and SEQ64_KEYSTROKE_RELEASE readability macros.

12.29.4.2 unsigned int seq64::keystroke::m_key [private]

Generally, the extended ASCII range (0 to 255) is supported. However, Gtk-2.x/3.x will generally support the full gamut of characters defined in the gdk_basic_keys.h module. We define minimum and maximum range macros for keystrokes that are a bit generous.

12.29.4.3 seq_modifier_t seq64::keystroke::m_modifier [private]

Note that SEQ64_NO_MASK is our word for 0, meaning "no modifier".

12.30 seq64::lash Class Reference

This class supports LASH operations, if compiled with LASH support (i.e.

Public Member Functions

- lash (perform &p, int argc, char **argv)
  This constructor calls lash_extract(), using the command-line arguments, if SEQ64_LASH_SUPPORT is enabled.
- void set_alsa_client_id (int id)
  Make ourselves a LASH ALSA client.
- void start ()
  Process any LASH events every 250 msec, which is an arbitrarily chosen interval.
- bool process_events ()
  Process LASH events.

Private Member Functions

- bool init ()
  Initializes LASH support, if enabled.
- void handle_event (lash_event_t *conf)
  Handle a LASH event.
- void handle_config (lash_config_t *conf)
  Handle a LASH configuration item.

Private Attributes

- perform & m_perform

  A hook into the single perform object in the application.
- lash_client_t * m_client

  Holds the client "handle" returned by the lash_init() function.
- lash_args_t * m_lash_args

  Holds the command-line arguments used by the lash_init() function.
- bool m_is_lash_supported

  Indicates if LASH support has been compiled into the library.

12.30.1 Detailed Description

SEQ64_LASH_SUPPORT is defined). All of the ifdef skeleton work is done in this class in such a way that any other part of the code can use this class whether or not lash support is actually built in; the functions will just do nothing.

12.30.2 Constructor & Destructor Documentation

12.30.2.1 seq64::lash::lash (perform & *p*, int *argc*, char ** *argv*)

We fixed the crazy usage of argc and argv here and in the client code in the seq24 module.

Parameters

p	The perform object that needs to implement LASH support.
argc	The number of command-line arguments.
argv	The command-line arguments.

12.30.3 Member Function Documentation

12.30.3.1 void seq64::lash::set_alsa_client_id (int *id*)

/param id The ALSA client ID to be set.

12.30.3.2 void seq64::lash::start ( )

12.30.3.3 bool seq64::lash::process_events ( )

Returns

Always returns true.

12.30.3.4 bool seq64::lash::init ( ) [private]

Returns

Returns true if the LASH subsystem was able to be initialized, and a LASH client representative (m_client) was allocated.

12.30.3.5 void seq64::lash::handle_event (lash_event_t * *ev*) [private]

Parameters

ev	Provides the event to be handled.

12.30.3.6 void seq64::lash::handle_config (lash_config_t * *conf*) [private]

Currently incomplete.

Parameters

conf	Provides the configuration item to handle.

12.30.4 Field Documentation

12.30.4.1 perform& seq64::lash::m_perform [private]

12.30.4.2 lash_client_t* seq64::lash::m_client [private]

12.30.4.3 lash_args_t* seq64::lash::m_lash_args [private]

12.30.4.4 bool seq64::lash::m_is_lash_supported [private]

Is set to true if SEQ64_LASH_SUPPORT is defined. This variable is not used, but we will keep it around for the possibility of testing LASH support at run time.

12.31 seq64::maintime Class Reference

This class provides the drawing of the progress bar at the top of the main window, along with two "pills" that move in time with the beat and measure.

Inheritance diagram for seq64::maintime:



Public Member Functions

- maintime (perform &p, int ppqn=SEQ64_USE_DEFAULT_PPQN)

  This constructor sets up the colors black, white, and grey, and then allocates them.
- virtual ~maintime ()

  Let's provide a do-nothing virtual destructor.

Private Member Functions

- maintime (const maintime &)
- maintime & operator= (const maintime &)
- int idle_progress (midipulse ticks)

  This function clears the window, sets the foreground to black, draws the "time" window's rectangle, and then draws a rectangle for noting the progress of the beat, and the progress for a bar.
- void on_realize ()

  Handles realization of the window.
- bool on_expose_event (GdkEventExpose ∗ev)

  This function merely idles.

Private Attributes

- const int m_beat_width

  Provides the divisor for ticks to produce a beat value.
- const int m_bar_width

  Provides the divisor for ticks to produce a bar value.
- const int m_pill_width

  Provides the width of the pills, little black squares that show the progress of a beat and a bar (measure).
- const int m_box_width

  The width/length of the rectangle to be drawn inside the maintime window.
- const int m_box_height

  The height of the rectangle to be drawn inside the maintime window.
- const int m_flash_width

  The width/length of the flashing rectangle to be drawn inside the maintime window.
- const int m_flash_height

  The height of the flashing rectangle to be drawn inside the maintime window.
- const int m_flash_x

  The x value at which a flash should occur.
- const int m_box_less_pill

  The width/length of the maintime window minus the width of the pill.
- midipulse m_tick

  Saves the tick value for on_expose_event().
- int m_ppqn

  Provides the active PPQN value.

Friends

- class mainwnd

Additional Inherited Members

12.31.1 Detailed Description

We added a lot of members to hold the results of calculations that involve what are essentially constant. This saves CPU time, and maybe a little memory for the code to make those calculations more than once.

12.31.2 Constructor & Destructor Documentation

12.31.2.1 seq64::maintime::maintime (const maintime &) [private]

12.31.2.2 seq64::maintime::maintime (perform & *p*, int *ppqn* = SEQ64_USE_DEFAULT_PPQN)

In the constructor you can only allocate colors; get_window() would return 0 because the windows has not yet been realized.

12.31.2.3 virtual seq64::maintime::~maintime ( ) [inline], [virtual]

12.31.3 Member Function Documentation

12.31.3.1 maintime& seq64::maintime::operator= (const maintime &) [private]

12.31.3.2 int seq64::maintime::idle_progress (midipulse *ticks*) [private]

Idle hands do the devil's work. We should eventually support some generic coloring for "dark themes". The default coloring is better for "light themes".

Parameters

ticks	Provides the main tick setting. This setting is provided by mainwnd(), in its timer callback.

Returns

Always returns 1 (it used to return "true"!).

12.31.3.3 void seq64::maintime::on_realize ( ) [private]

It performs the base class's on_realize() function. It then allocates some additional resources: a window, a GC (?), and it clears the window. Then it sets the default size of the window, specified by GUI constructor parameters.

12.31.3.4 bool seq64::maintime::on_expose_event (GdkEventExpose * *a_e*) [private]

We don't need the m_tick member, the function works as well if 0 is passed in. We've removed m_tick permanently.

Actually, it might be useful after all, to avoid flickering under JACK transport. Let's put it back for now. (It doesn't help, but we will leave it in, the overhead is small.)

12.31.4 Friends And Related Function Documentation

12.31.4.1 friend class mainwnd [friend]

12.31.5 Field Documentation

12.31.5.1 const int seq64::maintime::m_beat_width [private]

Currently, this value is hardwired to 4, but will eventually be wired up as usr().midi_beat_width().

12.31.5.2 const int seq64::maintime::m_bar_width [private]

Currently, this value is hardwired to 16, but will eventually be wired up as usr().midi_beat_width() * usr().midi_↩ beats_per_bar().

12.31.5.3 const int seq64::maintime::m_pill_width [private]

12.31.5.4 const int seq64::maintime::m_box_width [private]

This item absolutely depends on the main window being non-resizable.

12.31.5.5 const int seq64::maintime::m_box_height [private]

This item absolutely depends on the main window being non-resizable.

12.31.5.6 const int seq64::maintime::m_flash_width [private]

Just a bit smaller than m_box_width.

12.31.5.7 const int seq64::maintime::m_flash_height [private]

Just a bit smaller than m_box_width.

12.31.5.8 const int seq64::maintime::m_flash_x [private]

12.31.5.9 const int seq64::maintime::m_box_less_pill [private]

12.31.5.10 midipulse seq64::maintime::m_tick [private]

It might actually be useful after all. And the overhead is tiny.

12.31.5.11 int seq64::maintime::m_ppqn [private]

While this is effectively a constant for the duration of a tune, it might change as different tunes are loaded.

12.32 seq64::mainwid Class Reference

This class implements the piano roll area of the application.

Inheritance diagram for seq64::mainwid:



Public Member Functions

- mainwid (perform &p)

This constructor sets all of the members.

- virtual ~mainwid ()

  A rote destructor.

- void set_screenset (int ss, bool setperf=false)

  Set the current screen-set.

Private Member Functions

- void reset ()

  This function redraws everything and queues up a redraw operation.

- void update_sequences_on_window ()

  Updates the image of multiple sequencer/pattern slots.

- void draw_pixmap_on_window ()

  This function queues the blit of pixmap to window.

- void fill_background_window ()

  This function updates the background window, clearing it.

- virtual void redraw (int seq)

  This virtual function, overridden from the seqmenu base class, draws the the given pattern/sequence again.

- virtual void seq_set_and_edit (int seqnum)

  Calculates the sequence number based on the screenset and then calls the base-class function to bring up the pattern/sequence editor.

- virtual void seq_set_and_eventedit (int seqnum)

  Calculates the sequence number based on the screenset and then calls the base-class function to bring up the event editor.

- void draw_marker_on_sequence (int seq, int tick)

  Does the actual drawing of one pattern/sequence position marker, a vertical progress bar.

- void update_markers (int ticks)

  Draw the cursors (long vertical bars) on each sequence, so that they follow the playing progress of each sequence in the mainwid (Patterns Panel).

- bool valid_sequence (int seq)

  Common-code helper function.

- void draw_sequence_on_pixmap (int seq)

  This function draws a specific pattern/sequence on the pixmap located in the main window of the application, the Patterns Panel.

- void draw_sequences_on_pixmap ()

  This function fills the pixmap with sequences.

- void draw_sequence_pixmap_on_window (int seq)

  This function draws a sequence pixmap in the Patterns Panel.

- int seq_from_xy (int x, int y)

  Translates XY coordiinates in the Patterns Panel to a sequence number.

- int timeout ()

  Provides a stock callback, because some kind of callback is needed.

- void calculate_base_sizes (int seq, int &basex, int &basey)

  Provides a way to calculate the base x and y size values for the pattern map.

- void select_fg_bg_colors (int seqnum)

  Picks the foreground and background colors based on the sequence in edit and the SEQ64_EDIT_SEQUENCE_↩ HIGHLIGHT macro.

- void on_realize ()

  For this GTK callback, on realization of window, initialize the shiz.

- bool on_expose_event (GdkEventExpose *ev)

  Implements the GTK expose event callback.

- bool on_button_press_event (GdkEventButton ∗ev)

  Handles a press of a mouse button in one of the sequence/pattern slots.
- bool on_button_release_event (GdkEventButton ∗ev)

  Handles a release of a mouse button.
- bool on_motion_notify_event (GdkEventMotion ∗p0)

  Handle the motion of the mouse if a mouse button is down and in another sequence and if the current sequence is not in edit mode.
- bool on_focus_in_event (GdkEventFocus ∗)

  Handles an on-focus event.
- bool on_focus_out_event (GdkEventFocus ∗)

  Handles an out-of-focus event.

Private Attributes

- sequence m_moving_seq

  Holds a partial copy of the sequence we are moving on the patterns panel.
- bool m_button_down

  Indicates that the mouse button is still down.
- bool m_moving

  Indicates that we are still in the middle of a drag-and-drop operation.
- int m_old_seq

  Holds the sequence number of a sequence being drag-and-dropped.
- int m_screenset

  Indicates the current screenset that is visible.
- long m_last_tick_x [c_max_sequence]

  Holds the last active tick for each sequence, used in erasing the progress bar.
- int m_mainwnd_rows

  These values are assigned to the values given by the constants of similar names in globals.h, and we will make them parameters or user-interface configuration items later.
- int m_mainwnd_cols

  Number of columns, unused in settings.
- int m_seqarea_x

  Roughly with width of the main window.
- int m_seqarea_y

  Roughly with height of the main window.
- int m_seqarea_seq_x

  To be determined.
- int m_seqarea_seq_y

  To be determined.
- int m_mainwid_x

  To be determined.
- int m_mainwid_y

  To be determined.
- int m_mainwid_border

  Main-window border, unused setting.
- int m_mainwid_spacing

  Main-window spacing, unused setting.
- int m_text_size_x

  Text width, varies with font in use.
- int m_text_size_y

Text height, varies with font in use.

- int m_max_sets

  The maximum number of sets, use all over.

- int m_screenset_slots

  Provides a convenience variable for avoiding multiplications.

- int m_screenset_offset

  Provides a convenience variable for avoiding multiplications.

- int m_progress_height

  Provides the height of the progress bar, to save calculations and for consistency between drawing and erasing the progress bar.

Friends

- class mainwnd
- void update_mainwid_sequences ()

  This global function in the seq64 namespace calls mainwid :: update_sequences_on_window(), if the global mainwid object exists.

Additional Inherited Members

12.32.1 Detailed Description

It inherits from gui_drawingarea_gtk2 to support the font, color, and other GUI functionality, and from seqmenu to support the right-click Edit/New/Cut right-click menu. The friend class and function are for updating the current sequence and for control via the mainwnd object.

12.32.2 Constructor & Destructor Documentation

12.32.2.1 seq64::mainwid::mainwid (perform & *p*)

And it asks for a size of c_mainwid_x by c_mainwid_y. It adds GDK masks for button presses, releases, motion, key presses, and focus changes. Also logs a self-referential singleton pointer to use for the current-edit highlighting support.

Parameters

p	Provides the reference to the all-important perform object.

12.32.2.2 seq64::mainwid::~mainwid ( ) [virtual]

12.32.3 Member Function Documentation

12.32.3.1 void seq64::mainwid::set_screenset (int *ss*, bool *setperf* = false)

The clamping algorithm for the screeset is a bit weird: if less than 0, we set m_screenset to its maximum, and if greater than the maximum, we set it to its minimum. Not sure if this matters.

Note that m_screenset_slots = m_mainwnd_rows * m_mainwnd_cols.

We will likely replace this with perform::set_screenset(), which recapitulates the code above completely, whereas perform::set-offset() recapitulates only the line of code immediately above it. However, note that there is a back-and-forth between setting the screenset via perform (using MIDI control) versus the GUI in the mainwnd class. Probably useful to add a default boolean to prevent circular manipulation.

Parameters

ss	Provides the screen-set number to set.

12.32.3.2 void seq64::mainwid::reset ( ) [inline], [private]

12.32.3.3 void seq64::mainwid::update_sequences_on_window ( ) [inline], [private]

Used by the friend class mainwnd, but also useful for our new feature to fully highlight the current sequence. Calls reset() if SEQ64_EDIT_SEQUENCE_HIGHLIGHT is defined.

12.32.3.4 void seq64::mainwid::draw_pixmap_on_window ( ) [inline], [private]

12.32.3.5 void seq64::mainwid::fill_background_window ( ) [inline], [private]

12.32.3.6 void seq64::mainwid::redraw (int *seqnum*) [private], [virtual]

Parameters

seqnum	Provides the number of the sequence to draw.

Implements seq64::seqmenu.

12.32.3.7 void seq64::mainwid::seq_set_and_edit (int *seqnum*) [private], [virtual]

Used with the '=' key selection, by default.

Reimplemented from seq64::seqmenu.

12.32.3.8 void seq64::mainwid::seq_set_and_eventedit (int *seqnum*) [private], [virtual]

Used with the '-' key selection, by default.

Reimplemented from seq64::seqmenu.

12.32.3.9 void seq64::mainwid::draw_marker_on_sequence (int *seqnum*, int *tick*) [private]

If the sequence has no events, this function doesn't bother even drawing a position marker.

Note that, when Sequencer64 first comes up, and perform::is_dirty_main() is called, no sequences exist yet. Also, currently the redraw() is hit when seq_edit() is called, but not when seq_event_edit() is called, which makes the latter not paint the in-edit highlight colors (if enabled). Why?

Parameters

seqnum	Provides the number of the sequence to draw.
tick	Provides the location to draw the marker. If pause support is compiled in (i.e. no –disable-pause in the configuration), then this parameter is ignored, and is replaced by the sequences' get_lask_tick() value. This causes correct stop/pause/play progress-bar behavior in each pattern slot.

12.32.3.10 void seq64::mainwid::update_markers (int *tick*) [private]

Parameters

tick	Starting point for drawing the markers.

12.32.3.11 bool seq64::mainwid::valid_sequence (int *seqnum*) [private]

Parameters

seqnum	Provides the number of the sequence to validate.

Returns

Returns true if the sequence number is valid for the current m_screenset value.

12.32.3.12 void seq64::mainwid::draw_sequence_on_pixmap (int *seqnum*) [private]

The sequence is drawn only if it is in the current screen set (indicated by m_screenset). Also, we ignore the sequence if it does not exist.

Note

If only the main window is up, then the sequences just play (muted by default) – the progress bars move in each pattern. Gaps in the sequence in the Song (performance) Editor don't change the appearance of the patterns if only the main window is up. But, if the Song Editor window is up, and the song is started using the controls in the Song Editor, then the active patterns are black while playing, and white when gaps in the sequence are encountered. The muting status in the main window is ignored. The muting in the Song (performance) windows is in force. This setup holds for ALSA, but not for JACK transport.

Parameters

seqnum	Provides the number of the sequence slot that needs to be drawn. It is checked for validity before usage.

12.32.3.13 void seq64::mainwid::draw_sequences_on_pixmap ( ) [private]

Please note that draw_sequence_on_pixmap() also draws the empty slots of inactive sequences, so we cannot take shortcuts here.

12.32.3.14 void seq64::mainwid::draw_sequence_pixmap_on_window (int *seqnum*) [private]

The sequence is drawn only if it is in the current screen set (indicated by m_screenset. This function is used when dragging a pattern from one pattern-slot to another pattern-slot.

We have to add 1 pixel to the y height in order to avoid leaving behind a line at the bottom of an empty pattern-slot.

Parameters

seqnum	Provides the number of the sequence to draw.

12.32.3.15 int seq64::mainwid::seq_from_xy (int *x*, int *y*) [private]

Parameters

x	Provides the x coordinate.
y	Provides the y coordinate.

Returns

Returns -1 if the sequence number cannot be calculated.

12.32.3.16 int seq64::mainwid::timeout ( ) [private]

Todo We should use this callback to display the current time in the playback.

Returns

Always returns true.

12.32.3.17 void seq64::mainwid::calculate_base_sizes (int *seqnum*, int & *basex*, int & *basey*) [private]

The values are returned as side-effects.

Parameters

	seqnum	Provides the number of the sequence to calculate.
out	*basex*	A return parameter for the x coordinate of the base size.
out	*basey*	A return parameter for the y coordinate of the base size.

12.32.3.18 void seq64::mainwid::select_fg_bg_colors (int *seqnum*) [private]

12.32.3.19 void seq64::mainwid::on_realize ( ) [private]

It allocates any additional resources that weren't initialized in the constructor.

This function used to call font::init(), and was the only place where the font::init() function was called. The init() function gets a color-map from the window. We need a more fool-proof was to do this!

12.32.3.20 bool seq64::mainwid::on_expose_event (GdkEventExpose * *ev*) [private]

Parameters

ev	The expose event.

Returns

Always returns true.

12.32.3.21 bool seq64::mainwid::on_button_press_event (GdkEventButton * *ev*) [private]

If the press is a single left-click, and no Ctrl key is pressed, then this function grabs the focus, calculates the pattern/sequence over which the button press occurred, and sets the m_button_down flag if it is over a pattern. In the release event callback, this then causes the sequence arming/muting to be toggled.

If the press is a single Ctrl-left-click, this function brings up the New or Edit menu. The New menu is brought up if the grid slot is empty, and the Edit menu otherwise. Another way to bring up the same functionality is described in the next paragraph.

If the press is a double-click, it first acts just like two single-clicks (which might confuse the user at first, because it toggles the mute state twice). Then it brings up the Edit menu for the sequence. This new behavior is closer to what users have come to expect from a double-click. I miss the double-click when running seq24.

We also try to handle a Ctrl-double-click as a signal to do an event edit, instead of a sequence edit. The event editor provides a way to look at all events in detail, without having to select the type of event to see. However, this doesn't work, the event is treated like a ctrl-single-click. And we use the Alt key to enable window movement or resizing in our window manager, so that's out.

Parameters

ev	Provides the parameters of the button event.

Returns

Always returns true.

12.32.3.22 bool seq64::mainwid::on_button_release_event (GdkEventButton * *ev*) [private]

This event is a lot more complex than a press. The left button toggles playback status. The right button brings up a popup menu. If the slot is empty, then a "New" popup is presented, otherwise an "Edit" and selection popup is presented.

Also now implements the new "toggle all other patterns" action, initiated via Shift-Left-Click.

Parameters

ev	Provides the parameters of the button event.

Returns

Always returns true.

Tried disabling the setting of the current sequence; it completely disables drag-n-drop. But leaving it in removes the current-sequence highlighting, which otherwise is fine. So we do it only if moving a pattern (drag-and-drop).

12.32.3.23 bool seq64::mainwid::on_motion_notify_event (GdkEventMotion * *ev*) [private]

This function moves the selected pattern to another pattern slot. The perform::delete_sequence() function sets the perform modification flag.

Parameters

ev	Provides the parameters of the button event.

Returns

Always returns true.

12.32.3.24 bool seq64::mainwid::on_focus_in_event (GdkEventFocus *) [private]

Just sets the Gtk::HAS_FOCUS flag.

Returns

Always returns false.

12.32.3.25 bool seq64::mainwid::on_focus_out_event (GdkEventFocus *) [private]

Just unsets the Gtk::HAS_FOCUS flag.

Returns

Always returns false.

12.32.4 Friends And Related Function Documentation

12.32.4.1 friend class mainwnd [friend]

12.32.4.2 void update_mainwid_sequences ( ) [friend]

It is used by other objects that can modify the currently-edited sequence shown in the mainwid (main window).

12.32.5 Field Documentation

12.32.5.1 sequence seq64::mainwid::m_moving_seq [private]

The assignment is made by sequence::partial_copy(), which behaves like the legacy seq24 code.

12.32.5.2 bool seq64::mainwid::m_button_down [private]

Used in the drag-and-drop functionality.

12.32.5.3 bool seq64::mainwid::m_moving [private]

12.32.5.4 int seq64::mainwid::m_old_seq [private]

12.32.5.5 int seq64::mainwid::m_screenset [private]

12.32.5.6 long seq64::mainwid::m_last_tick_x[c_max_sequence] [private]

12.32.5.7 int seq64::mainwid::m_mainwnd_rows [private]

Some of them already have counterparts in the user_settings class.Number of rows, unused part of settings.

12.32.5.8 int seq64::mainwid::m_mainwnd_cols [private]

12.32.5.9 int seq64::mainwid::m_seqarea_x [private]

12.32.5.10 int seq64::mainwid::m_seqarea_y [private]

12.32.5.11 int seq64::mainwid::m_seqarea_seq_x [private]

12.32.5.12 int seq64::mainwid::m_seqarea_seq_y [private]

12.32.5.13 int seq64::mainwid::m_mainwid_x [private]

12.32.5.14 int seq64::mainwid::m_mainwid_y [private]

12.32.5.15 int seq64::mainwid::m_mainwid_border [private]

12.32.5.16 int seq64::mainwid::m_mainwid_spacing [private]

12.32.5.17 int seq64::mainwid::m_text_size_x [private]

12.32.5.18 int seq64::mainwid::m_text_size_y [private]

12.32.5.19 int seq64::mainwid::m_max_sets [private]

12.32.5.20 int seq64::mainwid::m_screenset_slots [private]

It is equal to m_mainwnd_rows $*$ m_mainwnd_cols.

12.32.5.21 int seq64::mainwid::m_screenset_offset [private]

It is equally to m_screenset_slots * m_screenset.

12.32.5.22 int seq64::mainwid::m_progress_height [private]

12.33 seq64::mainwnd Class Reference

This class implements the functionality of the main window of the application, except for the Patterns Panel functionality, which is implemented in the mainwid class.

Inheritance diagram for seq64::mainwnd:



Public Member Functions

- mainwnd (perform &a_p, bool allowperf2=true, int ppqn=SEQ64_USE_DEFAULT_PPQN)

  The constructor the main window of the application.
- virtual ~mainwnd ()

  This destructor must explicitly delete some allocated resources.
- void open_file (const std::string &filename)

Opens and parses (reads) a MIDI file.

- int ppqn () const

  'Getter' function for member m_ppqn

- void ppqn (int ppqn)

  'Setter' function for member m_ppqn We can't set the PPQN value when the mainwnd is created, we have to do it later, using this function.

Private Member Functions

- void file_import_dialog ()

  Presents a file dialog to import a MIDI file.

- void options_dialog ()

  Opens the File / Options dialog.

- void about_dialog ()

  Presents a Help / About dialog.

- void adj_callback_ss ()

  This function is the callback for adjusting the screen-set value.

- void adj_callback_bpm ()

  This function is the callback for adjusting the BPM value.

- void edit_callback_notepad ()

  A callback function for handling an edit to the screen-set notepad.

- bool timer_callback ()

  This function is the GTK timer callback, used to draw our current time and BPM on_events (the main window).

- void set_image (bool isrunning)

  Changes the image used for the pause/play button.

- void start_playing ()

  Starts playing of the song.

- void pause_playing ()

  Pauses the playing of the song, leaving the progress bar where it stopped.

- void stop_playing ()

  Stops the playing of the song.

- void toggle_playing ()

  Reverses the state of playback.

- void learn_toggle ()

  Toggle the group-learn status.

- void open_performance_edit ()

  Opens the Performance Editor (Song Editor).

- void open_performance_edit_2 ()

  Opens the second Performance Editor (Song Editor).

- void enregister_perfedits ()

  This function brings together the two perfedit objects, so that they can tell each other when to queue up a draw operation.

- void sequence_key (int seq)

  Use the sequence key to toggle the playing of an active pattern in the current screen-set.

- void update_window_title ()

  Updates the title shown in the title bar of the window.

- void toLower (std::string &)

  Converts a string to lower-case letters.

- void file_new ()

  A callback function for the File / New menu entry.

- void file_open ()

  A callback function for the File / Open menu entry.
- void file_save ()

  A callback function for the File / Save menu entry.
- void file_save_as ()

  A callback function for the File / Save As menu entry.
- void file_exit ()

  A callback function for the File / Exit menu entry.
- void new_file ()

  Actually does the work of setting up for a new file.
- bool save_file ()

  Saves the current state in a MIDI file.
- void choose_file ()

  Creates a file-chooser dialog.
- int query_save_changes ()

  Queries the user to save the changes made while the application was running.
- bool is_save ()

  If the data is modified, then the user is queried, and the file is save if okayed.
- bool install_signal_handlers ()

  Installs the signal handlers and pipe code.
- bool signal_action (Glib::IOCondition condition)

  Handles saving or exiting actions when signalled.
- bool on_delete_event (GdkEventAny *a_e)

  This callback function handles a delete event from ...?
- bool on_key_press_event (GdkEventKey *a_ev)

  Handles a key press event.
- bool on_key_release_event (GdkEventKey *a_ev)

  Handles a key release event.
- virtual void on_grouplearnchange (bool state)

  Notification handler for learn mode toggle.

Static Private Member Functions

- static void handle_signal (int sig)

  This function is the handler for system signals (SIGUSR1, SIGINT...) It writes a message to the pipe and leaves as soon as possible.

Private Attributes

- Gtk::Tooltips * m_tooltips

  A repository for tooltips.
- Gtk::MenuBar * m_menubar

  Theses objects support the menu and its sub-menus.
- Gtk::Menu * m_menu_file

  The File menu entry.
- Gtk::Menu * m_menu_view

  The View menu entry.
- Gtk::Menu * m_menu_help

  The Help menu entry.

- int m_ppqn

  Saves the PPQN value obtained from the MIDI file (or the default value, the global ppqn, if SEQ64_USE_DEFAUL↩ T_PPQN was specified in reading the MIDI file.
- mainwid * m_main_wid

  The biggest sub-components of mainwnd.
- maintime * m_main_time

  Is this the bar at the top that shows moving squares, also known as "pills"? Why yes, it is.
- perfedit * m_perf_edit

  A pointer to the first song/performance editor.
- perfedit * m_perf_edit_2

  A pointer to an optional second song/performance editor.
- options * m_options

  A pointer to the program options.
- Gdk::Cursor m_main_cursor

  Mouse cursor?
- Gtk::Image * m_image_play

  Provides a pointer to hold the images for the pause/play button.
- Gtk::Button * m_button_learn

  This button is the learn button, otherwise known as the "L" button.
- Gtk::Button * m_button_stop

  Implements the red square stop button.
- Gtk::Button * m_button_play

  Implements the green triangle play button.
- Gtk::Button * m_button_perfedit

  The button for bringing up the Song Editor (Performance Editor).
- Gtk::Adjustment * m_adjust_bpm

  The spin/adjustment controls for the BPM (beats-per-minute) value.
- Gtk::SpinButton * m_spinbutton_bpm

  BPM spin-button object.
- Gtk::Adjustment * m_adjust_ss

  The spin/adjustment controls for the screenset value.
- Gtk::SpinButton * m_spinbutton_ss

  Screenset adjustment.
- Gtk::Adjustment * m_adjust_load_offset

  The spin/adjustment controls for the load offset value.
- Gtk::SpinButton * m_spinbutton_load_offset

  Spin button for import.
- Gtk::Entry * m_entry_notes

  This item provides user-interface access to the screenset notepad editor.
- bool m_is_running

  Holds the current status of running, for use in display the play versus pause icon.
- sigc::connection m_timeout_connect

  Provides a timeout handler.
- bool m_call_seq_edit

  Indicates that this object is in a mode where the usual mute/unmute keystroke will instead bring up the pattern slot for editing.
- bool m_call_seq_eventedit

  Indicates that this object is in a mode where the usual mute/unmute keystroke will instead bring up the pattern slot for event-editing.

Static Private Attributes

- static int m_sigpipe [2]

  This small array holds the "handles" for the pipes need to intercept the system signals SIGINT and SIGUSR1, so that the application shuts down gracefully when aborted.

Additional Inherited Members

12.33.1 Constructor & Destructor Documentation

12.33.1.1 seq64::mainwnd::mainwnd (perform & *p,* bool *allowperf2* = `true`, int *ppqn* = `SEQ64_USE_DEFAULT_PPQN`)

This constructor is way too large; it would be nicer to provide a number of well-named initialization functions.

Parameters

p	Refers to the main performance object.
allowperf2	Indicates if a second perfedit window should be created. This is currently a run-time option, selectable in the "user" configuration file.
ppqn	An optional PPQN value to use in the song.

Todo Offload most of the work into an initialization function like options does; make the perform parameter a reference; valgrind flags m_tooltips as lost data, but if we try to manage it ourselves, many more leaks occur.

View menu items and their hot keys.

View menu items and their hot keys.

Help menu items

Top panel items, including the logo (updated for the new version of this application) and the "timeline" progress bar.

12.33.1.2 seq64::mainwnd::~mainwnd ( ) `[virtual]`

12.33.2 Member Function Documentation

12.33.2.1 void seq64::mainwnd::open_file (const std::string & *fn*)

We leave the ppqn parameter set to the SEQ64_USE_DEFAULT for now, to preserve the legacy behavior of using the global ppqn, and scaling the running time against the PPQN read from the MIDI file. Later, we can provide a value like 0, that will certainly be changed by reading the MIDI file.

We don't need to specify the "oldformat" or "global sequence" parameters of the midifile constructor when reading the MIDI file, since reading handles both the old and new formats, dealing with new constructs only if they are present in the file.

Parameters

fn	Provides the file-name for the MIDI file to be opened.

12.33.2.2 int seq64::mainwnd::ppqn ( ) const [inline]

12.33.2.3 void seq64::mainwnd::ppqn (int *ppqn*) [inline]

m_ppqn = choose_ppqn(ppqn);

12.33.2.4 void seq64::mainwnd::handle_signal (int *sig*) [static], [private]

12.33.2.5 void seq64::mainwnd::file_import_dialog ( ) [private]

Note that every track of the MIDI file will be imported, even if the track is only a label track (without any MIDI events), or a very long track.

The main difference between the Open operation and the Import operation seems to be that the latter can read MIDI files into a screen-set greater than screen-set 0. No, that's not true, so far. No matter what the current screen-set setting, the import is appended after the current data in screen-set 0. Then, if it overflows that screen-set, the overflow goes into the next screen-set.

It might be nice to have the option of importing a MIDI file into a specific screen-set, for better organization, as well as being able to offset the sequence number.

Also, it is important to note that perf().clear_all() is not called by this routine, as we are merely adding to what might already be there.

12.33.2.6 void seq64::mainwnd::options_dialog ( ) [private]

12.33.2.7 void seq64::mainwnd::about_dialog ( ) [private]

I (Chris) took the liberty of tacking my name at the end, and hope to have done eventually enough work to warrant having it there.

12.33.2.8 void seq64::mainwnd::adj_callback_ss ( ) [private]

Its sets the screen-set value in the Performance/Song window, the Patterns, and something about setting the text based on a screen-set notepad from the Performance/Song window. We let the perform object keep track of modifications.

12.33.2.9 void seq64::mainwnd::adj_callback_bpm ( ) [private]

Let the perform object keep track of modifications.

12.33.2.10 void seq64::mainwnd::edit_callback_notepad ( ) [private]

Let the perform object keep track of modifications.

12.33.2.11 bool seq64::mainwnd::timer_callback ( ) [private]

It also supports the ALSA pause functionality.

Note

When Sequencer64 first starts up, and no MIDI tune is loaded, the call to mainwid::update_markers() leads to trying to do some work on sequences that don't yet exist. Also, if a sequence is changed by the event editor, we get a crash; need to find out how seqedit gets away with the changes.

12.33.2.12 void seq64::mainwnd::set_image (bool *isrunning*) [private]

Parameters

isrunning	If true, set the image to the "Pause" icon, since playback is running. Otherwise, set it to the "Play" button, since playback is not running.

12.33.2.13 void seq64::mainwnd::start_playing ( ) [private]

The rc_settings::jack_start_mode() function is used (if jack is running) to determine if the playback mode is "live" (false) or "song" (true). An accessor to perform::start_playing(). This function is actually a callback for the pause/play button.

Note

This overrides the old behavior of playing live mode if the song is started from the main window. So let's go back to the way seq24 handles it. We could also make it dependent on the –legacy option, but that's too much trouble for now.

12.33.2.14 void seq64::mainwnd::pause_playing ( ) [private]

Currently, it is just the same as stop_playing(), but we will get it to work.

12.33.2.15 void seq64::mainwnd::stop_playing ( ) [private]

An accessor to perform's stop_playing() function. Also calls the mainwid::update_sequences_on_window() function. Not sure that we need this call, since the slots seem to update anyway. But we've noticed that, with this call in place, hitting the Stop button causes a subtle change in the appearance of the first non-empty pattern of the "allofarow.mid" file.

After the Stop button is pushed (in ALSA mode), then the Space key ("start") doesn't work properly. The song starts, then quickly stops. It doesn't matter if update_sequences_on_window() is called or not. This happens even in seq24! This bug has proven incredibly difficult to track down, still working on it.

12.33.2.16 void seq64::mainwnd::toggle_playing ( ) [private]

Meant only to be called when the "Play" button is pressed, if the pause feature has been compiled into the application.

12.33.2.17 void seq64::mainwnd::learn_toggle ( ) [inline], [private]

Simply forwards the call to perform::learn_toggle().

12.33.2.18 void seq64::mainwnd::open_performance_edit ( ) [private]

We will let perform keep track of modifications, and not just set an is-modified flag just because we opened the song editor. We're going to centralize the modification flag in the perform object, and see if it can work.

12.33.2.19 void seq64::mainwnd::open_performance_edit_2 ( ) [private]

Experiment: open a second one and see what happens. It works, but one needs to tell the other to redraw if a change is made.

12.33.2.20 void seq64::mainwnd::enregister_perfedits ( ) [private]

12.33.2.21 void seq64::mainwnd::sequence_key (int *seq*) [inline], [private]

12.33.2.22 void seq64::mainwnd::update_window_title ( ) [private]

Note that the name of the application is obtained by the "(SEQ64_PACKAGE)" construction.

The format of the caption bar is the name of the package/application, followed by the file-specification (shortened if necessary so that the name of the file itself can be seen), ending with the PPQN value in parentheses.

12.33.2.23 void seq64::mainwnd::toLower (std::string & *s*) [private]

12.33.2.24 void seq64::mainwnd::file_new ( ) [inline], [private]

12.33.2.25 void seq64::mainwnd::file_open ( ) [inline], [private]

12.33.2.26 void seq64::mainwnd::file_save ( ) [inline], [private]

12.33.2.27 void seq64::mainwnd::file_save_as ( ) [private]

12.33.2.28 void seq64::mainwnd::file_exit ( ) [private]

12.33.2.29 void seq64::mainwnd::new_file ( ) [private]

Not sure that we need to clear the modified flag here, especially since it is now centralizeed in the perform object. Let perf().clear_all() handle it now.

12.33.2.30 bool seq64::mainwnd::save_file ( ) [private]

Here we specify the current value of m_ppqn, which was set when reading the MIDI file. We also let midifile tell the perform that saving worked, so that the "is modified" flag can be cleared. The midifile class is already a friend of perform.

12.33.2.31 void seq64::mainwnd::choose_file ( ) [private]

12.33.2.32 int seq64::mainwnd::query_save_changes ( ) [private]

12.33.2.33 bool seq64::mainwnd::is_save ( ) [private]

12.33.2.34 bool seq64::mainwnd::install_signal_handlers ( ) [private]

12.33.2.35 bool seq64::mainwnd::signal_action (Glib::IOCondition *condition*) [private]

Returns

Returns true if the signalling was able to be completed, even if it was an unexpected signal.

12.33.2.36 bool seq64::mainwnd::on_delete_event (GdkEventAny * *a_e*) [private]

Any changed data is saved. If the pattern is playing, then it is stopped. We now use is_running(), instead of the global rc().is_pattern_playing() function.

12.33.2.37 bool seq64::mainwnd::on_key_press_event (GdkEventKey * *ev*) [private]

It also handles the control-key and modifier-key combinations matching the entries in its list of if statements.

Also, we now effectively press the CAPS LOCK key for the user if in group-learn mode, via the keystroke::shift_lock() function.

12.33.2.38 bool seq64::mainwnd::on_key_release_event (GdkEventKey * *ev*) [private]

Is this worth turning into a switch statement? Or offloading to a perform member function? The latter.

Also, we now effectively press the CAPS LOCK key for the user if in group-learn mode.

Todo Test this functionality in old and new application.

Returns

Always returns false. This matches seq24 behavior.

12.33.2.39 void seq64::mainwnd::on_grouplearnchange (bool *state*) [private], [virtual]

This handler responds to a learn-mode change from perf().

Reimplemented from seq64::performcallback.

12.33.3 Field Documentation

12.33.3.1 int seq64::mainwnd::m_sigpipe [static], [private]

This static member provides a couple of pipes for signalling/messaging.

12.33.3.2 Gtk::Tooltips* seq64::mainwnd::m_tooltips [private]

12.33.3.3 Gtk::MenuBar* seq64::mainwnd::m_menubar [private]

The whole menu bar.

12.33.3.4 Gtk::Menu* seq64::mainwnd::m_menu_file [private]

12.33.3.5 Gtk::Menu* seq64::mainwnd::m_menu_view [private]

12.33.3.6 Gtk::Menu* seq64::mainwnd::m_menu_help [private]

12.33.3.7 int seq64::mainwnd::m_ppqn [private]

We need it early here to be able to pass it along to child objects.

12.33.3.8 mainwid* seq64::mainwnd::m_main_wid [private]

The first is the Patterns Panel, which the mainwid helps implement. We end up sharing this object with perfedit, perfnames, and seqedit in order to allow the seqedit object to notify the mainwid (indirectly) of the currently-edited sequence.

12.33.3.9 maintime* seq64::mainwnd::m_main_time [private]

12.33.3.10 perfedit* seq64::mainwnd::m_perf_edit [private]

12.33.3.11 perfedit* seq64::mainwnd::m_perf_edit_2 [private]

The second makes it easy to line up two different patterns that cannot be seen together on one performance editor.

12.33.3.12 options* seq64::mainwnd::m_options [private]

12.33.3.13 Gdk::Cursor seq64::mainwnd::m_main_cursor [private]

12.33.3.14 Gtk::Image* seq64::mainwnd::m_image_play [private]

12.33.3.15 Gtk::Button* seq64::mainwnd::m_button_learn [private]

12.33.3.16 Gtk::Button* seq64::mainwnd::m_button_stop [private]

12.33.3.17 Gtk::Button* seq64::mainwnd::m_button_play [private]

If configured to support pause, it also supports the pause pixmap and functionality.

12.33.3.18 Gtk::Button* seq64::mainwnd::m_button_perfedit [private]

12.33.3.19 Gtk::Adjustment* seq64::mainwnd::m_adjust_bpm [private]

BPM adjustment object.

12.33.3.20 Gtk::SpinButton* seq64::mainwnd::m_spinbutton_bpm [private]

12.33.3.21 Gtk::Adjustment* seq64::mainwnd::m_adjust_ss [private]

Screenset adjustment.

12.33.3.22 Gtk::SpinButton* seq64::mainwnd::m_spinbutton_ss [private]

12.33.3.23 Gtk::Adjustment* seq64::mainwnd::m_adjust_load_offset [private]

These controls are used in the File / Import dialog to change where the imported file will be loaded in the sequences space, which ranges from 0 to 1024 in blocks of 32 patterns.Load number for import.

12.33.3.24 Gtk::SpinButton* seq64::mainwnd::m_spinbutton_load_offset [private]

12.33.3.25 Gtk::Entry* seq64::mainwnd::m_entry_notes [private]

This is just a long text-edit field that can be used to enter a long name or a short description of the current screenset.

12.33.3.26 bool seq64::mainwnd::m_is_running [private]

12.33.3.27 sigc::connection seq64::mainwnd::m_timeout_connect [private]

12.33.3.28 bool seq64::mainwnd::m_call_seq_edit [private]

Currently, the hard-wired key for this function is the equals key.

12.33.3.29 bool seq64::mainwnd::m_call_seq_eventedit [private]

Currently, the hard-wired key for this function is the minus key.

12.34 seq64::mastermidibus Class Reference

The class that "supervises" all of the midibus objects?

Public Member Functions

- mastermidibus (int ppqn=SEQ64_USE_DEFAULT_PPQN, int bpm=c_beats_per_minute)

  The mastermidibus default constructor fills the array with our busses.
- ~mastermidibus ()

  The destructor deletes all of the output busses, clears out the ALSA events, stops and frees the queue, and closes ALSA for this application.
- void init (int ppqn)

  Initialize the mastermidibus.
- snd_seq_t * get_alsa_seq () const

  'Getter' function for member m_alsa_seq
- int get_num_out_buses () const

  'Getter' function for member m_num_out_buses
- int get_num_in_buses () const

  'Getter' function for member m_num_in_buses
- void set_beats_per_minute (int bpm)

  Set the BPM value (beats per minute).
- void set_ppqn (int ppqn)

  Set the PPQN value (parts per quarter note).
- int get_beats_per_minute () const

  'Getter' function for member m_beats_per_minute
- int get_ppqn () const

  'Getter' function for member m_ppqn
- std::string get_midi_out_bus_name (int bus)

  Get the MIDI output buss name for the given (legal) buss number.
- std::string get_midi_in_bus_name (int bus)

  Get the MIDI input buss name for the given (legal) buss number.
- void print ()

  Print some information about the available MIDI output busses.
- void flush ()

  Flushes our local queue events out into ALSA.

- void start ()

  Starts all of the configured output busses up to m_num_out_buses.
- void stop ()

  Stops each of the output busses.
- void clock (midipulse tick)

  Generates the MIDI clock for each of the output busses.
- void continue_from (midipulse tick)

  Gets the output busses running again, if ALSA support is enabled.
- void init_clock (midipulse tick)

  Initializes the clock of each of the output busses.
- int poll_for_midi ()

  Initiate a poll() on the existing poll descriptors.
- bool is_more_input ()

  Test the ALSA sequencer to see if any more input is pending.
- bool get_midi_event (event *in)

  Grab a MIDI event.
- void set_sequence_input (bool state, sequence *seq)

  Set the input sequence object, and set the m_dumping_input value to the given state.
- bool is_dumping () const

  'Getter' function for member m_dumping_input
- sequence * get_sequence () const

  'Getter' function for member m_seq
- void sysex (event *event)

  Handle the sending of SYSEX events.
- void port_start (int client, int port)

  Start the given ALSA MIDI port.
- void port_exit (int client, int port)

  Turn off the given port for the given client.
- void play (bussbyte bus, event *e24, midibyte channel)

  Handle the playing of MIDI events on the MIDI buss given by the parameter, as long as it is a legal buss number.
- void set_clock (bussbyte bus, clock_e clock_type)

  Set the clock for the given (legal) buss number.
- clock_e get_clock (bussbyte bus)

  Gets the clock setting for the given (legal) buss number.
- void set_input (bussbyte bus, bool inputing)

  Set the status of the given input buss, if a legal buss number.
- bool get_input (bussbyte bus)

  Get the input for the given (legal) buss number.

Private Attributes

- snd_seq_t * m_alsa_seq

  The ALSA sequencer client handle.
- int m_num_out_buses

  The number of output busses.
- int m_num_in_buses

  The number of input busses.
- midibus * m_buses_out [c_max_busses]

  Output MIDI busses.
- midibus * m_buses_in [c_max_busses]

Input MIDI busses.

- midibus * m_bus_announce

  MIDI buss announcer?

- bool m_buses_out_active [c_max_busses]

  Active output MIDI busses.

- bool m_buses_in_active [c_max_busses]

  Active input MIDI busses.

- bool m_buses_out_init [c_max_busses]

  Output MIDI buss initialization.

- bool m_buses_in_init [c_max_busses]

  Input MIDI buss initialization.

- clock_e m_init_clock [c_max_busses]

  Clock initialization.

- bool m_init_input [c_max_busses]

  Input initialization?

- int m_queue

  The ID of the MIDI queue.

- int m_ppqn

  Resolution in parts per quarter note.

- int m_beats_per_minute

  BPM (beats per minute).

- int m_num_poll_descriptors

  The number of descriptors for polling.

- struct pollfd * m_poll_descriptors

  Points to the list of descriptors for polling.

- bool m_dumping_input

  For dumping MIDI input to a sequence for recording.

- sequence * m_seq

  Points to the sequence object.

- mutex m_mutex

  The locking mutex.

12.34.1 Constructor & Destructor Documentation

12.34.1.1 seq64::mastermidibus::mastermidibus (int *ppqn* = SEQ64_USE_DEFAULT_PPQN, int *bpm* = c_beats_per_minute)

Parameters

ppqn	Provides the PPQN value for this object. However, in most cases, the default, SEQ64_USE_DEFAULT_PPQN should be specified. Then the caller of this constructor should call mastermidibus::set_ppqn() to set up the proper PPQN value.
bpm	Provides the beats per minute value, which defaults to c_beats_per_minute.

12.34.1.2 seq64::mastermidibus::~mastermidibus ( )

Valgrind indicates we might have issues caused by the following functions:

- snd_config_hook_load()

```
-   snd_config_update_r() via snd_seq_open()
-   _dl_init() and other GNU function
-   init_gtkmm_internals() [version 2.4]
```

12.34.2 Member Function Documentation

12.34.2.1 void seq64::mastermidibus::init (int *ppqn*)

It initializes 16 MIDI output busses, a hardwired constant, SEQ64_ALSA_OUTPUT_BUSS_MAX == 16. Only one MIDI input buss is initialized.

Parameters

ppqn	The PPQN value to which to initialize the master MIDI buss.

12.34.2.2 snd_seq_t* seq64::mastermidibus::get_alsa_seq ( ) const [inline]

12.34.2.3 int seq64::mastermidibus::get_num_out_buses ( ) const [inline]

12.34.2.4 int seq64::mastermidibus::get_num_in_buses ( ) const [inline]

12.34.2.5 void seq64::mastermidibus::set_beats_per_minute (int *bpm*)

This is done by creating an ALSA tempo structure, adding tempo information to it, and then setting the ALSA sequencer object with this information.

We fill the ALSA tempo structure (snd_seq_queue_tempo_t) with the current tempo information, set the BPM value, put it in the tempo structure, and give the tempo value to the ALSA queue.

Threadsafe

Parameters

bpm	Provides the beats-per-minute value to set.

12.34.2.6 void seq64::mastermidibus::set_ppqn (int *ppqn*)

This is done by creating an ALSA tempo structure, adding tempo information to it, and then setting the ALSA sequencer object with this information. Fills the tempo structure with the current tempo information. Then sets the ppqn value. Finally, gives the tempo structure to the ALSA queue.

Threadsafe

Parameters

ppqn	The PPQN value to be set.

12.34.2.7 int seq64::mastermidibus::get_beats_per_minute ( ) const [inline]

12.34.2.8 int seq64::mastermidibus::get_ppqn ( ) const [inline]

12.34.2.9 std::string seq64::mastermidibus::get_midi_out_bus_name (int *bus*)

Parameters

bus	Provides the output buss number.

Returns

Returns the buss name as a standard C++ string, truncated to 80-1 characters. Also contains an indication that the buss is disconnected or unconnected.

12.34.2.10 std::string seq64::mastermidibus::get_midi_in_bus_name (int *bus*)

Parameters

bus	Provides the input buss number.

Returns

Returns the buss name as a standard C++ string, truncated to 80-1 characters. Also contains an indication that the buss is disconnected or unconnected.

12.34.2.11 void seq64::mastermidibus::print ( )

12.34.2.12 void seq64::mastermidibus::flush ( )

Threadsafe

12.34.2.13 void seq64::mastermidibus::start ( )

Threadsafe

12.34.2.14 void seq64::mastermidibus::stop ( )

If ALSA support is enable, also drains the output, synchronizes the output queue, and then stop the queue.

Threadsafe

12.34.2.15 void seq64::mastermidibus::clock (midipulse *tick*)

Threadsafe

Parameters

tick	Provides the tick value with which to set the buss clock.

12.34.2.16 void seq64::mastermidibus::continue_from (midipulse *tick*)

Threadsafe

Parameters

tick	Provides the tick value to continue from.

12.34.2.17 void seq64::mastermidibus::init_clock (midipulse *tick*)

Threadsafe

Parameters

tick	Provides the tick value with which to initialize the buss clock.

12.34.2.18 int seq64::mastermidibus::poll_for_midi ( )

Returns

Returns the result of the poll, or 0 if ALSA is not supported.

12.34.2.19 bool seq64::mastermidibus::is_more_input ( )

Threadsafe

Returns

Returns true if ALSA is supported, and the returned size is greater than 0, or false otherwise.

12.34.2.20 bool seq64::mastermidibus::get_midi_event (event * *inev*)

Threadsafe

Parameters

inev	The event to be set based on the found input event.

12.34.2.21 void seq64::mastermidibus::set_sequence_input (bool *state,* sequence * *seq*)

Threadsafe

Parameters

state	Provides the dumping-input state to be set.
seq	Provides the sequence object to be logged as the mastermidibus's sequence. Can also be used to set a null pointer, to disable the sequence setting.

12.34.2.22 bool seq64::mastermidibus::is_dumping ( ) const [inline]

12.34.2.23 sequence* seq64::mastermidibus::get_sequence ( ) const [inline]

12.34.2.24 void seq64::mastermidibus::sysex (event * *ev*)

Threadsafe

Parameters

ev	Provides the event pointer to be set.

12.34.2.25 void seq64::mastermidibus::port_start (int *client,* int *port*)

Threadsafe Quite a lot is done during the lock!

Parameters

client	Provides the ALSA client number.
port	Provides the ALSA client port.

12.34.2.26 void seq64::mastermidibus::port_exit (int *client,* int *port*)

Both the input and output busses for the given client are stopped, and set to inactive.

Threadsafe

Parameters

client	The client to be matched and acted on.
port	The port to be acted on. Both parameter must be match before the buss is made inactive.

12.34.2.27 void seq64::mastermidibus::play (bussbyte *bus*, event * *e24*, midibyte *channel*)

Threadsafe

Parameters

bus	The buss to start play on.
e24	The seq24 event to play on the buss.
channel	The channel on which to play the event.

12.34.2.28 void seq64::mastermidibus::set_clock (bussbyte *bus*, clock_e *clocktype*)

The legality checks are a little loose, however.

Threadsafe

Parameters

bus	The buss to start play on.
clocktype	The type of clock to be set, either "off", "pos", or "mod", as noted in the midibus_common module.

12.34.2.29 clock_e seq64::mastermidibus::get_clock (bussbyte *bus*)

Parameters

bus	Provides the buss number to read.

Returns

If the buss number is legal, and the buss is active, then its clock setting is returned. Otherwise, e_clock_off is returned.

12.34.2.30 void seq64::mastermidibus::set_input (bussbyte *bus*, bool *inputing*)

Why is another buss-count constant, and a global one at that, being used? And I thought there was only one input buss anyway! Well, there is only one ALSA input buss, but more can be used with JACK, apparently.

Threadsafe

Parameters

bus	Provides the buss number.
inputing	True if the input bus will be inputting MIDI data.

12.34.2.31 bool seq64::mastermidibus::get_input (bussbyte *bus*)

Parameters

bus	Provides the buss number.

Returns

Always returns false.

12.34.3 Field Documentation

12.34.3.1 snd_seq_t* seq64::mastermidibus::m_alsa_seq [private]

12.34.3.2 int seq64::mastermidibus::m_num_out_buses [private]

12.34.3.3 int seq64::mastermidibus::m_num_in_buses [private]

12.34.3.4 midibus* seq64::mastermidibus::m_buses_out[c_max_busses] [private]

12.34.3.5 midibus* seq64::mastermidibus::m_buses_in[c_max_busses] [private]

12.34.3.6 midibus* seq64::mastermidibus::m_bus_announce [private]

12.34.3.7 bool seq64::mastermidibus::m_buses_out_active[c_max_busses] [private]

12.34.3.8 bool seq64::mastermidibus::m_buses_in_active[c_max_busses] [private]

12.34.3.9 bool seq64::mastermidibus::m_buses_out_init[c_max_busses] [private]

12.34.3.10 bool seq64::mastermidibus::m_buses_in_init[c_max_busses] [private]

12.34.3.11 clock_e seq64::mastermidibus::m_init_clock[c_max_busses] [private]

12.34.3.12 bool seq64::mastermidibus::m_init_input[c_max_busses] [private]

12.34.3.13 int seq64::mastermidibus::m_queue [private]

12.34.3.14 int seq64::mastermidibus::m_ppqn [private]

12.34.3.15 int seq64::mastermidibus::m_beats_per_minute [private]

We had to lengthen this name; way too easy to confuse it with "bpm" for "beats per measure".

12.34.3.16 int seq64::mastermidibus::m_num_poll_descriptors [private]

12.34.3.17 struct pollfd* seq64::mastermidibus::m_poll_descriptors [private]

12.34.3.18 bool seq64::mastermidibus::m_dumping_input [private]

12.34.3.19 sequence* seq64::mastermidibus::m_seq [private]

12.34.3.20 mutex seq64::mastermidibus::m_mutex [private]

This object is passed to an automutex object that lends exception-safety to the mutex locking.

12.35 seq64::midi_container Class Reference

This class is the abstract base class for a container of MIDI track information.

Inheritance diagram for seq64::midi_container:



Public Member Functions

- midi_container (sequence &seq)

  Fills in the few members of this class.
- virtual ~midi_container ()

  A rote constructor needed for a base class.
- void fill (int tracknumber)

  This function fills the given track (sequence) with MIDI data from the current sequence, preparatory to writing it to a file.
- virtual std::size_t size () const

  Returns the size of the container, in midibytes.
- virtual bool done () const

  Instead of checking for the size of the container when "emptying" it [see the midifile::write() function], use this function, which is overridden to match the type of container being used.
- virtual void put (midibyte b)=0

  Provides a way to add a MIDI byte into the container.
- virtual midibyte get ()=0

  Provide a way to get the next byte from the container.

Protected Member Functions

- unsigned int position_reset () const

  'Setter' function for member m_position_for_get Sets the position to 0 and then returns that value.
- unsigned int position () const

  'Getter' function for member m_position_for_get Returns the current position.
- void position_increment () const

  'Getter' function for member m_position_for_get Increments the current position.

Private Member Functions

- void add_variable (midipulse v)

  This function masks off the lower 8 bits of the long parameter, then shifts it right 7, and, if there are still set bits, it encodes it into the buffer in reverse order.
- void add_long (midipulse x)

  Adds a long value (a MIDI pulse/tick value) to the container.

Private Attributes

- sequence & m_sequence

  Provide a hook into a sequence so that we can exchange data with a sequence object.
- unsigned int m_position_for_get

  Provides the position in the container when making a series of get() calls on the container.

12.35.1 Detailed Description

It is the base class for midi_list and midi_vector.

12.35.2 Constructor & Destructor Documentation

12.35.2.1 seq64::midi_container::midi_container (sequence & *seq*)

Parameters

seq	Provides a reference to the sequence/track for which this container holds MIDI data.

12.35.2.2 virtual seq64::midi_container::~midi_container ( ) [inline], [virtual]

12.35.3 Member Function Documentation

12.35.3.1 void seq64::midi_container::fill (int *tracknumber*)

Note that some of the events might not come out in the same order they were stored in (we see that with program-change events). This function replaces sequence::fill_container().

Now, for sequence 0, an alternate format for writing the sequencer number chunk is "FF 00 00". But that format can only occur in the first track, and the rest of the tracks then don't need a sequence number, since it is assume to increment. This application doesn't use with that shortcut.

Triggers:

```
Triggers are added by first calling add_variable(0), which is needed
because why?

Then 0xFF 0x7F is written, followed by the length value, which is the
number of triggers at 3 long integers per trigger, plus the 4-byte
code for triggers, c_triggers_new = 0x24240008.
```

Not threadsafe The sequence object bound to this container needs to provide the locking mechanism when calling this function.

Parameters

tracknumber	Provides the track number. This number is masked into the track information.

New feature: save more sequence-specific values, if not legacy format and not saved globally. We use a single byte for the key and scale, and a long for the background sequence. We save these values only if they are different from the defaults; in most cases they will have been left alone by the user. We save per-sequence values here only if the global-background-sequence feature is not in force.

12.35.3.2 virtual std::size_t seq64::midi_container::size ( ) const [inline], [virtual]

Must be overridden in the derived class, though not pure.

Reimplemented in seq64::midi_list, and seq64::midi_vector.

12.35.3.3 virtual bool seq64::midi_container::done ( ) const [inline], [virtual]

Reimplemented in seq64::midi_vector, and seq64::midi_list.

12.35.3.4 virtual void seq64::midi_container::put (midibyte *b*) [pure virtual]

The original seq24 container used an std::list and a push_front operation.

Implemented in seq64::midi_vector, and seq64::midi_list.

12.35.3.5 virtual midibyte seq64::midi_container::get ( ) [pure virtual]

It also increments m_position_for_get.

Implemented in seq64::midi_vector, and seq64::midi_list.

12.35.3.6 unsigned int seq64::midi_container::position_reset ( ) const [inline], [protected]

12.35.3.7 unsigned int seq64::midi_container::position ( ) const [inline], [protected]

12.35.3.8 void seq64::midi_container::position_increment ( ) const [inline], [protected]

12.35.3.9 void seq64::midi_container::add_variable (midipulse *v*) [private]

This function "replaces" sequence::add_list_var().

Parameters

v	The data value to be added to the current event in the MIDI container.

12.35.3.10 void seq64::midi_container::add_long (midipulse *x*) [private]

What is the difference between this function and add_list_var()? This function "replaces" sequence::add_long_list(). This was a *global* internal function called addLongList(). Let's at least make it a private member now, and hew to the naming conventions of this class.

Parameters

x	Provides the timestamp (pulse value) to be added to the container.

12.35.4 Field Documentation

12.35.4.1 sequence& seq64::midi_container::m_sequence [private]

12.35.4.2 unsigned int seq64::midi_container::m_position_for_get [mutable], [private]

12.36 seq64::midi_control Class Reference

This class (formerly a struct) contains the control information for sequences that make up a live set.

Public Member Functions

- midi_control ()

  This default constructor creates a "zero" object.
- bool active () const
- bool inverse_active () const
- int status () const
- int data () const
- int min_value () const
- int max_value () const
- void set (int values[6])

  Not so sure if this really saves trouble for the caller.
- void set (midibyte values[6])

  Not so sure if this really saves trouble for the caller.
- bool match (midibyte status, midibyte data) const

  Handles a common check in the perform module.
- bool in_range (midibyte data) const

  Handles a common check in the perform module.

Private Attributes

- bool m_active

  Provides the value for active.
- bool m_inverse_active

  Provides the value for inverse-active.
- int m_status

  Provides the value for the status.
- int m_data

  Provides the value for the data.
- int m_min_value

  Provides the minimum value for the controller.
- int m_max_value

  Provides the value for the controller.

12.36.1 Detailed Description

Note that, although we've converted this to a full-fledged class, the ordering of variables and the data arrays used to fill them is very signifcant. See the midifile and optionsfile modules.

The perform module sets up the three following arrays for each of the MIDI controls that can be defined in the "rc" file:

```
    m_midi_cc_toggle[]
    m_midi_cc_on[]
    m_midi_cc_off[]


These three arrays are specified in the "rc" by a line like the following:


    n [0 0   0   0   0   0] [0 0   0   0   0   0] [0 0   0   0   0   0]
```

```
where n ranges from 0 to 73.  Lines 0 to 31 provide controller values for
the "pattern group", one line for each of the 32 pattern slots.
Lines 32 to 63 provide controller values for
the "mute in group", one line for each of the 32 pattern slots.
The rest of the lines provide entries for control of:
BPM up, BPM down, Screen-set up, Screen-set down, Mod Replaces, Mod
Snapshot, Mod Queue, Mod gmute (group mute), Mod glearn (group learn),
and Screen-set Play.

In each of the bracketed sections, the values correspond to the members in
this order: m_active, m_inverse_active, m_status, m_data, m_min_value, and
m_max_value.

Why are the status, data, and min/max values long?  A character or
midibyte would be enough.  We'll fix that later, once we have tested this
stuff.  We do need to convert them from long to int, though, and do that
in the scanning and output done by optionsfile.
```

12.36.2 Constructor & Destructor Documentation

12.36.2.1 seq64::midi_control::midi_control ( ) [inline]

Every member is either false or zero.

12.36.3 Member Function Documentation

12.36.3.1 bool seq64::midi_control::active ( ) const [inline]

12.36.3.2 bool seq64::midi_control::inverse_active ( ) const [inline]

12.36.3.3 int seq64::midi_control::status ( ) const [inline]

12.36.3.4 int seq64::midi_control::data ( ) const [inline]

12.36.3.5 int seq64::midi_control::min_value ( ) const [inline]

12.36.3.6 int seq64::midi_control::max_value ( ) const [inline]

12.36.3.7 void seq64::midi_control::set (int *values[6]*) [inline]

It fits in with the big-ass sscanf() call in optionsfile.

Parameters

values	Provides the six values, in an integer array, to set into the members in this order: m_active, m_inverse_active, m_status, m_data, m_min_value, and m_max_value.

12.36.3.8 void seq64::midi_control::set (midibyte *values[6]*) [inline]

It fits in with the usage in midifile.

Parameters

values	Provides the six values, in a byte array, to set into the members in this order: m_active, m_inverse_active, m_status, m_data, m_min_value, and m_max_value.

12.36.3.9 bool seq64::midi_control::match (midibyte *status*, midibyte *data*) const [inline]

Parameters

status	Provides the status byte, which is checked against m_status.
data	Provides the data byte, which is checked against m_data.

12.36.3.10 bool seq64::midi_control::in_range (midibyte *data*) const [inline]

12.36.4 Field Documentation

12.36.4.1 bool seq64::midi_control::m_active [private]

12.36.4.2 bool seq64::midi_control::m_inverse_active [private]

12.36.4.3 int seq64::midi_control::m_status [private]

12.36.4.4 int seq64::midi_control::m_data [private]

12.36.4.5 int seq64::midi_control::m_min_value [private]

12.36.4.6 int seq64::midi_control::m_max_value [private]

12.37 seq64::midi_list Class Reference

This class is the std::list implementation of the midi_container.

Inheritance diagram for seq64::midi_list:



Public Member Functions

- midi_list (sequence &seq)

  This constructor fills in the members.
- virtual ~midi_list ()

  A rote constructor needed for a base class.
- virtual std::size_t size () const

  Returns the size of the container, in midibytes.
- virtual bool done () const

  For popping data from the MIDI list, we are done when the container is empty.
- virtual void put (midibyte b)

  Provides a way to add a MIDI byte into the list.
- virtual midibyte get ()

  Provide a way to get the next byte from the container.

Private Types

- typedef std::list< midibyte > CharList

  Provides the type of this container.

Private Attributes

- CharList m_char_list

  The container itself.

Additional Inherited Members

12.37.1 Member Typedef Documentation

12.37.1.1 typedef std::list<midibyte> seq64::midi_list::CharList [private]

This type is basically the same as the midifile::m_char_list container in the midifile module.

12.37.2 Constructor & Destructor Documentation

12.37.2.1 seq64::midi_list::midi_list (sequence & *seq*)

Parameters

seq	The sequence/track object that is using this container.

12.37.2.2 virtual seq64::midi_list::~midi_list ( ) [inline], [virtual]

12.37.3 Member Function Documentation

12.37.3.1 virtual std::size_t seq64::midi_list::size ( ) const [inline], [virtual]

Reimplemented from seq64::midi_container.

12.37.3.2 virtual bool seq64::midi_list::done ( ) const [inline], [virtual]

Reimplemented from seq64::midi_container.

12.37.3.3 virtual void seq64::midi_list::put (midibyte *b*) [inline], [virtual]

The original seq24 list used an std::list and a push_front operation.

Implements seq64::midi_container.

12.37.3.4 virtual midibyte seq64::midi_list::get ( ) [inline], [virtual]

In this implementation, m_position_for_get is not used. The elements of the container are popped off backward!

Implements seq64::midi_container.

12.37.4 Field Documentation

12.37.4.1 CharList seq64::midi_list::m_char_list [private]

12.38 seq64::midi_measures Class Reference

Provides a data structure to hold the numeric equivalent of the measures string "measures:beats:divisions" ("m:b↩:d").

Public Member Functions

- midi_measures ()
  Default constructor for midi_measures.
- midi_measures (int measures, int beats, int divisions)
  Principal constructor for midi_measures.
- int measures () const
  'Getter' function for member m_measures
- void measures (int m)
  'Setter' function for member m_measures
- int beats () const
  'Getter' function for member m_beats
- void beats (int b)
  'Setter' function for member m_beats
- int divisions () const
  'Getter' function for member m_divisions
- void divisions (int d)
  'Setter' function for member m_divisions

Private Attributes

- int m_measures
  The integral number of measures in the measures-based time.
- int m_beats
  The integral number of beats in the measures-based time.
- int m_divisions
  The integral number of divisions/pulses in the measures-based time.

12.38.1 Detailed Description

More commonly known as "bars:beats:ticks", or "BBT".

12.38.2 Constructor & Destructor Documentation

12.38.2.1 seq64::midi_measures::midi_measures ( )

12.38.2.2 seq64::midi_measures::midi_measures (int *measures*, int *beats*, int *divisions*)

Parameters

measures	Copied into the m_measures member.
beats	Copied into the m_beats member.
divisions	Copied into the m_divisions member.

12.38.3 Member Function Documentation

12.38.3.1 int seq64::midi_measures::measures ( ) const [inline]

12.38.3.2 void seq64::midi_measures::measures (int *m*) [inline]

Parameters

m	The value to which to set the number of measures. We can add validation later.

12.38.3.3 int seq64::midi_measures::beats ( ) const [inline]

12.38.3.4 void seq64::midi_measures::beats (int *b*) [inline]

Parameters

b	The value to which to set the number of beats. We can add validation later.

12.38.3.5 int seq64::midi_measures::divisions ( ) const [inline]

12.38.3.6 void seq64::midi_measures::divisions (int *d*) [inline]

Parameters

d	The value to which to set the number of divisions. We can add validation later.

12.38.4 Field Documentation

12.38.4.1 int seq64::midi_measures::m_measures [private]

12.38.4.2 int seq64::midi_measures::m_beats [private]

12.38.4.3 int seq64::midi_measures::m_divisions [private]

There are two possible translations of the two bytes of a division. If the top bit of the 16 bits is 0, then the time division is in "ticks per beat" (or “pulses per quarter note”). If the top bit is 1, then the time division is in "frames per second". This member deals only with the ticks/beat definition.

12.39 seq64::midi_splitter Class Reference

This class handles the parsing and writing of MIDI files.

Public Member Functions

- midi_splitter (int ppqn=SEQ64_USE_DEFAULT_PPQN)

  Principal constructor.
- ~midi_splitter ()

  A rote destructor.
- bool log_main_sequence (sequence &seq, int seqnum)

  Logs the main sequence (an SMF 0 track) for later usage in splitting the track.
- void initialize ()

  Resets the SMF 0 support variables in preparation for parsing a new MIDI file.
- void increment (int channel)

  Processes a channel number by raising its flag in the m_smf0_channels[] array.
- bool split (perform &p, int screenset)

  This function splits an SMF 0, splitting all of the channels in the sequence out into separate sequences, and adding each to the perform object.
- int ppqn () const

  'Getter' function for member m_ppqn Provides a way to get the actual value of PPQN used in processing the sequences when parse() was called.
- int count () const

  'Getter' function for member m_smf0_channels_count

Private Member Functions

- bool split_channel (const sequence &main_seq, sequence *seq, int channel)

  This function splits the given sequence into new sequences, one for each channel found in the SMF 0 track.

Private Attributes

- int m_ppqn

  Provides the current value of the PPQN, which used to be constant and is now only the macro DEFAULT_PPQN.
- bool m_use_default_ppqn

  Indicates that the default PPQN is in force.
- int m_smf0_channels_count

  Provides support for SMF 0, indicates how many channels were found in the file in a single sequence.
- bool m_smf0_channels [16]

  Provides support for SMF 0, holds a bool value that indicates the occurrence of a given channel.
- sequence * m_smf0_main_sequence

  Provides support for SMF 0, points to the initial SMF 0 sequence, from which the single-channel sequences will be created.
- int m_smf0_seq_number

  Provides support for SMF 0, holds the prospective sequence number of the main (SMF 0) sequence.

12.39.1 Detailed Description

In addition to the standard MIDI tracks, it also handles some "private" or "proprietary" tracks specific to Seq24. It does not, however, handle SYSEX events.

12.39.2 Constructor & Destructor Documentation

12.39.2.1 seq64::midi_splitter::midi_splitter (int *ppqn* = SEQ64_USE_DEFAULT_PPQN)

Parameters

ppqn	Provides the initial value of the PPQN setting. It is handled differently for parsing (reading) versus writing the MIDI file. • Reading. – If set to SEQ64_USE_DEFAULT_PPQN, the legacy application behavior is used. The m_ppqn member is set to the default PPQN, DEFAULT_PPQN. The value read from the MIDI file, ppqn, is then use to scale the running-time of the sequence relative to DEFAULT_PPQN. – Otherwise, m_ppqn is set to the value read from the MIDI file. No scaling is done. Since the value gets written, specify ppqn as 0, an obviously bogus value, to get this behavior. • Writing. This value is written to the MIDI file in the header chunk of the song. Note that the caller must query for the PPQN set during parsing, and pass it to the constructor when preparing to write the file. See how it is done in the mainwnd class.

12.39.2.2 seq64::midi_splitter::~midi_splitter ( )

12.39.3 Member Function Documentation

12.39.3.1 bool seq64::midi_splitter::log_main_sequence (sequence & *seq*, int *seqnum*)

/param seq The main sequence to be logged.

/param seqnum The sequence number of the main sequence.

/return Returns true if the main sequence's address was logged, and false if it was already logged.

12.39.3.2 void seq64::midi_splitter::initialize ( )

12.39.3.3 void seq64::midi_splitter::increment (int *channel*)

If it is the first entry for that channel, m_smf0_channels_count is incremented. We won't check the channel number, to save time, until someday we segfault :-D

Parameters

channel	The MIDI channel number. The caller is responsible to make sure it ranges from 0 to 15.

12.39.3.4 bool seq64::midi_splitter::split (perform & *p*, int *screenset*)

Lastly, it adds the SMF 0 track as the last track; the user can then examine it before removing it. Is this worth the effort?

There is a little oddity, in that, if the SMF 0 track has events for only one channel, this code will still create a new sequence, as well as the main sequence. Not sure if this is worth extra code to just change the channels on the main sequence and put it into the correct track for the one channel it contains. In fact, we just want to keep it in patter slot number 16, to keep it out of the way.

Parameters

p	Provides a reference to the perform object into which sequences/tracks are to be added.
screenset	The screen-set offset to be used when loading a sequence (track) from the file.

Returns

Returns true if the parsing succeeded. Returns false if no SMF 0 main sequence was logged.

12.39.3.5 int seq64::midi_splitter::ppqn ( ) const [inline]

The PPQN will be either the global ppqn (legacy behavior) or the value read from the file, depending on the ppqn parameter passed to the midi_splitter constructor.

12.39.3.6 int seq64::midi_splitter::count ( ) const [inline]

12.39.3.7 bool seq64::midi_splitter::split_channel (const sequence & *main_seq*, sequence * *s*, int *channel*) [private]

Note that the events that are read from the MIDI file have delta times. Sequencer64 converts these delta times to cumulative times. We need to preserve that here. Conversion back to delta times is needed only when saving the sequences to a file. This is done in midi_container::fill().

We have to accumulate the delta times in order to be able to set the length of the sequence in pulses.

Luckily, we don't have to worry about copying triggers, since the imported SMF 0 track won't have any Seq24/↩ Sequencer24 triggers.

It doesn't set the sequence number of the sequence; that is set when the sequence is added to the perform object.

Parameters

main_seq	This parameter is the whole SMF 0 track that was read from the MIDI file. It contains all of the channel data that needs to be split into separate sequences.
s	Provides the new sequence that needs to have its settings made, and all of the selected channel events added to it.
channel	Provides the MIDI channel number (re 0) that marks the channel data the needs to be extracted and added to the new sequence.

Returns

Returns true if at least one event got added. If none were added, the caller should delete the sequence object represented by parameter *s*.

12.39.4 Field Documentation

12.39.4.1 int seq64::midi_splitter::m_ppqn [private]

12.39.4.2 bool seq64::midi_splitter::m_use_default_ppqn [private]

12.39.4.3 int seq64::midi_splitter::m_smf0_channels_count [private]

SMF 1 file parsing will only warn about more than one channel found in a given sequence.

12.39.4.4 bool seq64::midi_splitter::m_smf0_channels[16] [private]

Obviously, we don't have to worry about multiple MIDI busses.

12.39.4.5 sequence* seq64::midi_splitter::m_smf0_main_sequence [private]

12.39.4.6 int seq64::midi_splitter::m_smf0_seq_number [private]

We want to be able to add that sequence last, for easier and cleaner removal of that sequence by the user.

12.40 seq64::midi_timing Class Reference

We anticipate the need to have a small structure holding the parameters needed to calculate MIDI times within an arbitrary song.

Public Member Functions

- midi_timing ()
  Defaults constructor for midi_timing.
- midi_timing (int bpminute, int bpmeasure, int beatwidth, int ppqn)
  Principal constructor for midi_timing.
- int beats_per_minute () const
  'Getter' function for member m_beats_per_minute
- void beats_per_minute (int b)
  'Setter' function for member m_beats_per_minute
- int beats_per_measure () const
  'Getter' function for member m_beats_per_measure
- void beats_per_measure (int b)
  'Setter' function for member m_beats_per_measure
- int beat_width () const
  'Getter' function for member m_beats_per_beat_width
- void beat_width (int bw)
  'Setter' function for member m_beats_per_beat_width
- int ppqn () const
  'Getter' function for member m_ppqn
- void ppqn (int p)
  'Setter' function for member m_ppqn

Private Attributes

- int m_beats_per_minute

  This value should match the BPM value selected when editing the song.
- int m_beats_per_measure

  This value should match the numerator value selected when editing the sequence.
- int m_beat_width

  This value should match the denominator value selected when editing the sequence.
- int m_ppqn

  This value provides the precision of the MIDI song.

12.40.1 Detailed Description

Although Seq24/Sequencer64 currently are heavily dependent on hard-wired values, that will be rectified eventually, so let us get ready for it.

12.40.2 Constructor & Destructor Documentation

12.40.2.1 seq64::midi_timing::midi_timing ( )

12.40.2.2 seq64::midi_timing::midi_timing (int *bpminute,* int *bpmeasure,* int *beatwidth,* int *ppqn*)

Parameters

bpminute	Copied into the m_beats_per_minute member.
bpmeasure	Copied into the m_beats_per_measure member.
beatwidth	Copied into the m_beat_width member.
ppqn	Copied into the m_ppqn member.

12.40.3 Member Function Documentation

12.40.3.1 int seq64::midi_timing::beats_per_minute ( ) const [inline]

12.40.3.2 void seq64::midi_timing::beats_per_minute (int *b*) [inline]

Parameters

b	The value to which to set the number of beats/minute. We can add validation later.

12.40.3.3 int seq64::midi_timing::beats_per_measure ( ) const [inline]

12.40.3.4 void seq64::midi_timing::beats_per_measure (int *b*) [inline]

Parameters

b	The value to which to set the number of beats/measure. We can add validation later.

12.40.3.5 int seq64::midi_timing::beat_width ( ) const [inline]

12.40.3.6 void seq64::midi_timing::beat_width (int *bw*) [inline]

Parameters

bw	The value to which to set the number of beats in the denominator of the time signature. We can add validation later.

12.40.3.7 int seq64::midi_timing::ppqn ( ) const [inline]

12.40.3.8 void seq64::midi_timing::ppqn (int *p*) [inline]

Parameters

p	The value to which to set the PPQN member. We can add validation later.

12.40.4 Field Documentation

12.40.4.1 int seq64::midi_timing::m_beats_per_minute [private]

This value is most commonly set to 120, but is also read from the MIDI file. This value is needed if one want to calculate durations in true time units such as seconds, but is not needed to calculate the number of pulses/ticks/divisions.

12.40.4.2 int seq64::midi_timing::m_beats_per_measure [private]

This value is most commonly set to 4.

12.40.4.3 int seq64::midi_timing::m_beat_width [private]

This value is most commonly set to 4, meaning that the fundamental beat unit is the quarter note.

12.40.4.4 int seq64::midi_timing::m_ppqn [private]

This value is most commonly set to 192, but is also read from the MIDI file. We are still working getting "non-standard" values to work.

12.41 seq64::midi_vector Class Reference

This class is the std::vector implementation of the midi_container.

Inheritance diagram for seq64::midi_vector:



Public Member Functions

- midi_vector (sequence &seq)

  This constructor fills in the members of this class.
- virtual ~midi_vector ()

  A rote constructor needed for a base class.
- virtual std::size_t size () const
- virtual bool done () const

  For iterating through the data in the MIDI vector, we are done when we've gotten the last element of the container.
- virtual void put (midibyte b)

  Provides a way to add a MIDI byte into the list.
- virtual midibyte get ()

  Provide a way to get the next byte from the container.

Private Types

- typedef std::vector< midibyte > CharVector

  Provides the type of this container.

Private Attributes

- CharVector m_char_vector

  The container itself.

Additional Inherited Members

12.41.1 Member Typedef Documentation

12.41.1.1 typedef std::vector<midibyte> seq64::midi_vector::CharVector [private]

12.41.2 Constructor & Destructor Documentation

12.41.2.1 seq64::midi_vector::midi_vector (sequence & *seq*)

Parameters

seq	Provides a reference to the sequence/track for which this container holds MIDI data.

12.41.2.2 virtual seq64::midi_vector::~midi_vector ( ) [inline], [virtual]

12.41.3 Member Function Documentation

12.41.3.1 virtual std::size_t seq64::midi_vector::size ( ) const [inline], [virtual]

Returns

Returns the size of the container, in midibytes.

Reimplemented from seq64::midi_container.

12.41.3.2 virtual bool seq64::midi_vector::done ( ) const [inline], [virtual]

Returns

Returns true if the position is greater than or equal to the size of the character vector.

Reimplemented from seq64::midi_container.

12.41.3.3 virtual void seq64::midi_vector::put (midibyte *b*) [inline], [virtual]

The original seq24 list used an std::list and a push_front operation.

Parameters

b	Provides the MIDI byte to push_back() into the character vector.

Implements seq64::midi_container.

12.41.3.4 virtual midibyte seq64::midi_vector::get ( ) [inline], [virtual]

In this implementation, m_position_for_get is used. As a side-effect, the position value is incremented.

Returns

Returns the next byte in the character vector.

Implements seq64::midi_container.

12.41.4 Field Documentation

12.41.4.1 CharVector seq64::midi_vector::m_char_vector [private]

12.42 seq64::midibus Class Reference

Provides a class for handling the MIDI buss on Linux.

Public Member Functions

- midibus (int localclient, int destclient, int destport, snd_seq_t *seq, const char *client_name, const char *port_name, int id, int queue, int ppqn=SEQ64_USE_DEFAULT_PPQN)
  Provides a constructor with client number, port number, ALSA sequencer support, name of client, name of port.
- midibus (int localclient, snd_seq_t *seq, int id, int queue, int ppqn=SEQ64_USE_DEFAULT_PPQN)
  Secondary constructor.
- ~midibus ()
  A rote empty destructor.
- bool init_out ()
  Initialize the MIDI output port.
- bool init_in ()
  Initialize the MIDI input port.
- bool deinit_in ()
  Deinitialize the MIDI input?
- bool init_out_sub ()
  Initialize the output in a different way?
- bool init_in_sub ()
  Initialize the output in a different way?
- void print ()
  Prints m_name.
- const std::string & get_name () const

'Getter' function for member n_name

- int get_id () const

  'Getter' function for member m_id

- void play (event *e24, midibyte channel)

  This play() function takes a native event, encodes it to an ALSA event, and puts it in the queue.

- void sysex (event *e24)

  Takes a native SYSEX event, encodes it to an ALSA event, and then puts it in the queue.

- void start ()

  This function gets the MIDI clock a-runnin', if the clock type is not e_clock_off.

- void stop ()

  Stop the MIDI buss.

- void clock (midipulse tick)

  Generates the MIDI clock, starting at the given tick value.

- void continue_from (midipulse tick)

  Continue from the given tick.

- void init_clock (midipulse tick)

  Initialize the clock, continuing from the given tick.

- void set_clock (clock_e clocktype)

  'Setter' function for member m_clock_type

- clock_e get_clock () const

  'Getter' function for member m_clock_type

- void set_input (bool inputing)

  Set status to of "inputting" to the given value.

- bool get_input () const

  'Getter' function for member m_inputing

- void flush ()

  Flushes our local queue events out into ALSA.

- int get_client () const

  'Getter' function for member m_dest_addr_client The address of client.

- int get_port () const

  'Getter' function for member m_dest_addr_port

Static Public Member Functions

- static void set_clock_mod (int clockmod)

  Set the clock mod to the given value, if legal.

- static int get_clock_mod ()

  Get the clock mod value.

Private Attributes

- int m_id

  The ID of the midibus object.

- clock_e m_clock_type

  The type of clock to use.

- bool m_inputing

  TBD.

- int m_ppqn

  Provides the PPQN value in force, currently a constant.

- snd_seq_t *const m_seq

  ALSA sequencer client handle.
- const int m_dest_addr_client

  Destination address of client.
- const int m_dest_addr_port

  Destination port of client.
- const int m_local_addr_client

  Local address of client.
- int m_local_addr_port

  Local port of client.
- int m_queue

  Another ID of the MIDI queue?
- std::string m_name

  The name of the MIDI buss.
- midipulse m_lasttick

  The last (most recent? final?) tick.
- mutex m_mutex

  Locking mutex.

Static Private Attributes

- static int m_clock_mod

  *This is another name for "16 * 4".*

Friends

- class mastermidibus

  The master MIDI bus sets up the buss.

12.42.1 Constructor & Destructor Documentation

12.42.1.1 seq64::midibus::midibus (int *localclient*, int *destclient*, int *destport*, snd_seq_t * *seq*, const char * *client_name*, const char * *port_name*, int *id*, int *queue*, int *ppqn* = SEQ64_USE_DEFAULT_PPQN)

Parameters

localclient	Provides the local-client number.
destclient	Provides the destination-client number.
destport	Provides the destination-client port.
seq	Provides the sequence that will work with this buss.
client_name	Provides the client name, but this parameter is unused.
port_name	Provides the port name.
id	Provides the ID code for this bus. It is an index into the midibus definitions array, and is also used in the constructed human-readable buss name.
queue	Provides the queue ID.
ppqn	Provides the PPQN value.

12.42.1.2 seq64::midibus::midibus (int *localclient,* snd_seq_t * *seq,* int *id,* int *queue,* int *ppqn* = SEQ64_USE_DEFAULT_PPQN)

Similar to the principal constructor, but labels the buss by number more than by name.

Parameters

localclient	Provides the local-client number.
seq	Provides the sequence that will work with this buss.
id	Provides the ID code for this bus. It is an index into the midibus definitions array, and is also used in the constructed human-readable buss name.
queue	Provides the queue ID.
ppqn	Provides the PPQN value.

12.42.1.3 seq64::midibus::~midibus ( )

12.42.2 Member Function Documentation

12.42.2.1 bool seq64::midibus::init_out ( )

Returns

Returns true unless setting up ALSA MIDI failed in some way.

12.42.2.2 bool seq64::midibus::init_in ( )

Returns

Returns true unless setting up ALSA MIDI failed in some way.

12.42.2.3 bool seq64::midibus::deinit_in ( )

Returns

Returns true, unless an error occurs.

12.42.2.4 bool seq64::midibus::init_out_sub ( )

Returns

Returns true unless setting up the ALSA port failed in some way.

12.42.2.5 bool seq64::midibus::init_in_sub ( )

Returns

Returns true unless setting up the ALSA port failed in some way.

12.42.2.6 void seq64::midibus::print ( )

12.42.2.7 const std::string& seq64::midibus::get_name ( ) const [inline]

12.42.2.8 int seq64::midibus::get_id ( ) const [inline]

12.42.2.9 void seq64::midibus::play (event * *e24,* midibyte *channel*)

Threadsafe

Parameters

e24	The event to be played on this bus.
channel	The channel of the playback.

12.42.2.10 void seq64::midibus::sysex (event * *e24*)

Parameters

e24	The event to be handled.

12.42.2.11 void seq64::midibus::start ( )

12.42.2.12 void seq64::midibus::stop ( )

12.42.2.13 void seq64::midibus::clock (midipulse *tick*)

Parameters

tick	Provides the starting tick.

12.42.2.14 void seq64::midibus::continue_from (midipulse *tick*)

Parameters

tick	The continuing tick.

12.42.2.15 void seq64::midibus::init_clock (midipulse *tick*)

Parameters

tick	The starting tick.

12.42.2.16 void seq64::midibus::set_clock (clock_e *clocktype*) [inline]

Parameters

clocktype	The value used to set the clock-type.

12.42.2.17 clock_e seq64::midibus::get_clock ( ) const [inline]

12.42.2.18 void seq64::midibus::set_input (bool *inputing*)

If the parameter is true, then init_in() is called; otherwise, deinit_in() is called.

Parameters

inputing	The inputing value to set.

12.42.2.19 bool seq64::midibus::get_input ( ) const [inline]

12.42.2.20 void seq64::midibus::flush ( )

12.42.2.21 int seq64::midibus::get_client ( ) const [inline]

12.42.2.22 int seq64::midibus::get_port ( ) const [inline]

12.42.2.23 static void seq64::midibus::set_clock_mod (int *clockmod*) [inline], [static]

Parameters

clockmod	If this value is not equal to 0, it is used to set the static member m_clock_mod.

12.42.2.24 static int seq64::midibus::get_clock_mod ( ) [inline], [static]

12.42.3 Friends And Related Function Documentation

12.42.3.1 friend class mastermidibus [friend]

12.42.4 Field Documentation

12.42.4.1 int seq64::midibus::m_clock_mod [static], [private]

Initialize this static member.

12.42.4.2 int seq64::midibus::m_id [private]

12.42.4.3 clock_e seq64::midibus::m_clock_type [private]

12.42.4.4 bool seq64::midibus::m_inputing [private]

12.42.4.5 int seq64::midibus::m_ppqn [private]

12.42.4.6 snd_seq_t* const seq64::midibus::m_seq [private]

12.42.4.7 const int seq64::midibus::m_dest_addr_client [private]

12.42.4.8 const int seq64::midibus::m_dest_addr_port [private]

12.42.4.9 const int seq64::midibus::m_local_addr_client [private]

12.42.4.10 int seq64::midibus::m_local_addr_port [private]

12.42.4.11 int seq64::midibus::m_queue [private]

12.42.4.12 std::string seq64::midibus::m_name [private]

12.42.4.13 midipulse seq64::midibus::m_lasttick [private]

12.42.4.14 mutex seq64::midibus::m_mutex [private]

12.43 seq64::midifile Class Reference

This class handles the parsing and writing of MIDI files.

Public Member Functions

- midifile (const std::string &name, int ppqn=SEQ64_USE_DEFAULT_PPQN, bool oldformat=false, bool globalbgs=true)

  Principal constructor.
- ~midifile ()

  A rote destructor.
- bool parse (perform &a_perf, int a_screen_set=0)

  This function opens a binary MIDI file and parses it into sequences and other application objects.
- bool write (perform &a_perf)

  Write the whole MIDI data and Seq24 information out to the file.
- const std::string & error_message () const

  'Getter' function for member m_error_message
- bool error_is_fatal () const

  'Getter' function for member m_error_is_fatal
- int ppqn () const

  'Getter' function for member m_ppqn Provides a way to get the actual value of PPQN used in processing the sequences when parse() was called.

Private Member Functions

- bool parse_smf_0 (perform &p, int screenset)

  This function parses an SMF 0 binary MIDI file as if it were an SMF 1 file, then, if more than one MIDI channel was encountered in the sequence, splits all of the channels in the sequence out into separate sequences.
- bool parse_smf_1 (perform &p, int screenset, bool is_smf0=false)

  This function parses an SMF 1 binary MIDI file; it is basically the original seq25 midifile::parse() function.
- midilong parse_prop_header (int file_size)

  Parse the proprietary header, figuring out if it is the new format, or the legacy format, for sequencer-specific data.
- bool parse_proprietary_track (perform &a_perf, int file_size)

  After all of the conventional MIDI tracks are read, we're now at the "proprietary" Seq24 data section, which describes the various features that Seq24 supports.
- int pow2 (int logbase2)

  Internal function for simple calculation of a power of 2 without a lot of math.
- bool checklen (midilong len, midibyte type)

  Internal function to check for and report a bad length value.
- void add_trigger (sequence &seq, midishort ppqn)

  Internal function to make the parser easier to read.
- midilong read_long ()

  Reads 4 bytes of data using read_byte().
- midishort read_short ()

  Reads 2 bytes of data using read_byte().
- midibyte read_byte ()

  Reads 1 byte of data directly from the m_data vector, incrementing m_pos after doing so.
- midilong read_varinum ()

  Read a MIDI Variable-Length Value (VLV), which has a variable number of bytes.
- void write_long (midilong value)

  Writes 4 bytes, each extracted from the long value and shifted rightward down to byte size, using the write_byte() function.
- void write_short (midishort value)

  Writes 2 bytes, each extracted from the long value and shifted rightward down to byte size, using the write_byte() function.
- void read_byte_array (midibyte *b, int len)

  A helper function to simplify reading midi_control data from the MIDI file.
- void write_byte (midibyte c)

  Writes 1 byte.
- void write_varinum (midilong)

  Writes a MIDI Variable-Length Value (VLV), which has a variable number of bytes.
- void write_track_name (const std::string &trackname)

  Writes out a track name.
- std::string read_track_name ()

  Reads the track name.
- void write_seq_number (midishort seqnum)

  Writes out a sequence number.
- int read_seq_number ()

  Reads the sequence number.
- void write_track_end ()

  Writes out the end-of-track marker.
- void write_prop_header (midilong tag, long len)

  We want to write:
- bool write_proprietary_track (perform &a_perf)

  Writes out the proprietary/SeqSpec section, using the new format if the legacy format is not in force.

- long varinum_size (long len) const

  Calculates the length of a variable length value.
- long prop_item_size (long datalen) const

  Calculates the size of a proprietary item, as written by the write_prop_header() function, plus whatever is called to write the data.
- long track_name_size (const std::string &trackname) const

  Calculates the size of a trackname and the meta event that specifies it.
- void errdump (const std::string &msg)

  Helper function to emit more useful error messages.
- void errdump (const std::string &msg, unsigned long p)

  Helper function to emit more useful error messages for erroneous long values.
- long seq_number_size () const

  Returns the size of a sequence-number event, which is always 5 bytes, plus one byte for the delta time that precedes it.
- long track_end_size () const

  Returns the size of a track-end event, which is always 3 bytes.
- bool is_sysex_special_id (midibyte ch)

  Check for special SysEx ID byte.

Private Attributes

- int m_file_size

  Holds the size of the MIDI file.
- std::string m_error_message

  Holds the last error message, useful for trouble-shooting without having Sequencer64 running in a console window.
- bool m_error_is_fatal

  Indicates if the error should be considered fatal.
- bool m_disable_reported

  Indicates that file reading has already been disabled (due to serious errors), so don't complain about it anymore.
- int m_pos

  Holds the position in the MIDI file.
- const std::string m_name

  The unchanging name of the MIDI file.
- std::vector< midibyte > m_data

  This vector of characters holds our MIDI data.
- std::list< midibyte > m_char_list

  Provides a list of characters.
- bool m_new_format

  Use the new format for the proprietary footer section of the Seq24 MIDI file.
- bool m_global_bgsequence

  Indicates to store the new key, scale, and background sequence in the global, "proprietary" section of the MIDI song.
- int m_ppqn

  Provides the current value of the PPQN, which used to be constant and is now only the macro DEFAULT_PPQN.
- bool m_use_default_ppqn

  Indicates that the default PPQN is in force.
- midi_splitter m_smf0_splitter

  Provides support for SMF 0.

12.43.1 Detailed Description

In addition to the standard MIDI tracks, it also handles some "private" or "proprietary" tracks specific to Seq24. It does not, however, handle SYSEX events.

12.43.2 Constructor & Destructor Documentation

12.43.2.1 seq64::midifile::midifile (const std::string & *name*, int *ppqn* = SEQ64_USE_DEFAULT_PPQN, bool *oldformat* = false, bool *globalbgs* = true)

Parameters

name	Provides the name of the MIDI file to be read or written.
ppqn	Provides the initial value of the PPQN setting. It is handled differently for parsing (reading) versus writing the MIDI file. • Reading. – If set to SEQ64_USE_DEFAULT_PPQN, the legacy application behavior is used. The m_ppqn member is set to the default PPQN, DEFAULT_PPQN. The value read from the MIDI file, ppqn, is then use to scale the running-time of the sequence relative to DEFAULT_PPQN. – Otherwise, m_ppqn is set to the value read from the MIDI file. No scaling is done. Since the value gets written, specify ppqn as 0, an obviously bogus value, to get this behavior. • Writing. This value is written to the MIDI file in the header chunk of the song. Note that the caller must query for the PPQN set during parsing, and pass it to the constructor when preparing to write the file. See how it is done in the mainwnd class.
oldformat	If true, write out the MIDI file using the old Seq24 format, instead of the new MIDI-compliant sequencer-specific format, for the seq24-specific SeqSpec tags defined in the globals module. This option is false by default. Note that this option is only used in writing; reading can handle either format transparently.
globalbgs	If true, write any non-default values of the key, scale, and background sequence to the global "proprietary" section of the MIDI file, instead of to each sequence. Note that this option is only used in writing; reading can handle either format transparently.

12.43.2.2 seq64::midifile::~midifile ( )

12.43.3 Member Function Documentation

12.43.3.1 bool seq64::midifile::parse (perform & *p*, int *screenset* = 0)

In addition to the standard MIDI track data in a normal track, Seq24/Sequencer64 adds four sequencer-specific events just before the end of the track:

```
c_triggers_new:     SeqSpec FF 7F 1C 24 24 00 08 00 00 ...
c_midibus:          SeqSpec FF 7F 05 24 24 00 01 00
c_timesig:          SeqSpec FF 7F 06 24 24 00 06 04 04
c_midich:           SeqSpec FF 7F 05 24 24 00 02 06
```

```
Note that only Sequencer64 adds "FF 7F len" to the SeqSpec data.

Standard MIDI provides for port and channel specification meta events, but
they are apparently considered obsolete:


    Obsolete meta-event:               Replacement:
    MIDI port (buss):   FF 21 01 po    Device (port) name: FF 09 len text
    MIDI channel:       FF 20 01 ch


What do other applications use for specifying port/channel?

Note the is-modified flag:  We now assume that the perform object is
starting from scratch when parsing.  But we let mainwnd tell the perform
object when to clear everything with perform::clear_all().  The mainwnd
does this for a new file, opening a file, but not for a file import, which
might be done simply to add more MIDI tracks to the current composition.
So, if parsing succeeds, all we want to do is make sure the flag is set.
Parsing a file successfully is not always a modification of the setup.
For instance, the first read of a MIDI file should start clean, not dirty.
```

SysEx notes:

```
Some files (e.g. Dixie04.mid) do not always encode System Exclusive
messages properly for a MIDI file.  Instead of a varinum length value,
they are followed by extended IDs (0x7D, 0x7E, or 0x7F).

We've covered some of those cases by disabling access to m_data if the
position passes the size of the file, but we want try to bypass these
odd cases properly.  So we look ahead for one of these special values.
```

Parameters

p	Provides a reference to the perform object into which sequences/tracks are to be added.
screenset	The screen-set offset to be used when loading a sequence (track) from the file. This value ranges from -31 to 0 to +31 (32 is the maximum screen-set available in Seq24). This offset is added to the sequence number read in for the sequence, to place it elsewhere in the imported tune, and locate it in a specific screen-set. If this parameter is non-zero, then we will assume that the perform data is dirty.

Returns

Returns true if the parsing succeeded. Note that the error status is saved in m_error_is_fatal, and a message (to display later) is saved in m_error_message.

12.43.3.2 bool seq64::midifile::write (perform & *p*)

Parameters

p	Provides the object that will contain and manage the entire performance.

Returns

Returns true if the write operations succeeded.

Note

Seq24 reverses the order of some events, due to popping from its container. Not an issue here.

12.43.3.3 const std::string& seq64::midifile::error_message ( ) const [inline]

12.43.3.4 bool seq64::midifile::error_is_fatal ( ) const [inline]

12.43.3.5 int seq64::midifile::ppqn ( ) const [inline]

The PPQN will be either the global ppqn (legacy behavior) or the value read from the file, depending on the ppqn parameter passed to the midifile constructor.

12.43.3.6 bool seq64::midifile::parse_smf_0 (perform & *p,* int *screenset*) [private]

The original sequence remains in place, in sequence slot 16 (the 17th slot). The user is responsible for deleting it if it is not needed.

Parameters

p	Provides a reference to the perform object into which sequences/tracks are to be added.
screenset	The screen-set offset to be used when loading a sequence (track) from the file.

Returns

Returns true if the parsing succeeded.

12.43.3.7 bool seq64::midifile::parse_smf_1 (perform & *p,* int *screenset,* bool *is_smf0* = false) [private]

It assumes the file-data has already been read into memory. It also assumes that the ID, track-length, and format have already been read.

Parameters

p	Provides a reference to the perform object into which sequences/tracks are to be added.
screenset	The screen-set offset to be used when loading a sequence (track) from the file.
is_smf0	True if we detected that the MIDI file is in SMF 0 format.

Returns

Returns true if the parsing succeeded.

12.43.3.8 midilong seq64::midifile::parse_prop_header (int *file_size*) [private]

The new format creates a final track chunk, starting with "MTrk". Then comes the delta-time (here, 0), and the event. An event is a MIDI event, a SysEx event, or a Meta event.

A MIDI Sequencer Specific meta message includes either a delta time or absolute time, and the MIDI Sequencer Specific event encoded as follows:

```
        0x00 0xFF 0x7F length data
```

```
For convenience, this function first checks the amount of file data left.
If enough, then it reads a long value.  If the value starts with 0x00 0xFF
0x7F, then that is a SeqSpec event, which signals usage of the new
Sequencer64 "proprietary" format.  Otherwise, it is probably the old
format, and the long value is a control tag (0x242400nn), which can be
returned immedidately.

If it is the new format, we back up to the FF, then get the next byte,
which should be a 7F.  If so, then we read the length (a variable
length value) of the data, and then read the long value, which should
be the control tag, which, again, is returned by this function.
```

Note

Most sequencers seem to be tolerant of both the lack of an "MTrk" marker and of the presence of an unwrapped control tag, and so can handle both the old and new formats of the final proprietary track.

Parameters

file_size	The size of the data file. This value is compared against the member m_pos (the position inside m_data[]), to make sure there is enough data left to process.

Returns

Returns the control-tag value found. These are the values, such as c_midich, found in the globals module, that indicate the type of sequencer-specific data that comes next. If there is not enough data to process, then 0 is returned.

12.43.3.9 bool seq64::midifile::parse_proprietary_track (perform & *p*, int *file_size*) [private]

It consists of series of tags:

```
        c_midictrl
        c_midiclocks
        c_notes
        c_bpmtag (beats per minute)
        c_mutegroups
        c_musickey (new, added if usr() global_seq_feature() is true)
        c_musicscale (ditto)
        c_backsequence (ditto)
```

```
(There are more tags defined in the globals module, but they are not
used in this function.  This doesn't quite make sense, as there are
also some "triggers" values, and we're pretty sure the application
uses them.  Oh, it turns out that they are set up by actions performed on
each sequence, and are stored as sequencer-specific ("SeqSpec") data with
each track's data as held in the MIDI container for the track.  See the
midi_container module for more information.)

The format is (1) tag ID; (2) length of data; (3) the data.
```

```
First, we separate out this function for a little more clarity.  Then we
added code to handle reading both the legacy Seq24 format and the new,
MIDI-compliant format.  Note that even the new format is not quite
correct, since it doesn't handle a MIDI manufacturer's ID, making it a
single byte that is part of the data.  But it does have the "MTrk" marker
and track name, so that must be processed for the new format.

Now, in our "midicvt" project, we have a test MIDI file,
b4uacuse-non-mtrk.midi that is good, except for having a tag "MUnk"
instead of "MTrk".  We should consider being more permissive, if possible.
Otherwise, though, the only penality is that the "proprietary" chunk is
completely skipped.
```

Parameters

p	The performance object that is being set via the incoming MIDI file.
file_size	The file size as determined in the parse() function.

There are also implicit parameters, with the m_pos and m_new_format member variables.

12.43.3.10 int seq64::midifile::pow2 (int *logbase2*) [private]

Use for calculating the denominator of a time signature.

Parameters

logbase2	Provides the power to which 2 is to be raised. This integer is probably only rarely greater than 4 (which represents a denominator of 16).

Returns

Returns 2 raised to the logbase2 power.

12.43.3.11 bool seq64::midifile::checklen (midilong *len,* midibyte *type*) [private]

Parameters

len	The length value to be checked, and it should be greater than 0.
type	The type of meta event. Used for displaying an error.

Returns

Returns true if the length parameter is valid.

12.43.3.12 void seq64::midifile::add_trigger (sequence & *seq,* midishort *ppqn*) [private]

Handles only c_triggers_new values, not the old c_triggers value. If m_ppqn isn't set to the default value, then we must scale these triggers accordingly, just as is done for the MIDI events.

Parameters

seq	Provides the sequence to which the trigger is to be added.
ppqn	Provides the ppqn value to use to scale the tick values if m_use_default_ppqn is true. If 0, the ppqn value is not used.

12.43.3.13 midilong seq64::midifile::read_long ( ) [private]

Warning

This code looks endian-dependent and integer-size dependent.

Returns

Returns the four bytes, shifted appropriately and added together, most-significant byte first, to sum to a long value.

12.43.3.14 midishort seq64::midifile::read_short ( ) [private]

Returns

Returns the two bytes, shifted appropriately and added together, most-significant byte first, to sum to a short value.

12.43.3.15 midibyte seq64::midifile::read_byte ( ) [private]

Returns

Returns the byte that was read. Returns 0 if there was an error, though there's no way for the caller to determine if this is an error or a good value.

12.43.3.16 midilong seq64::midifile::read_varinum ( ) [private]

This function reads the bytes while bit 7 is set in each byte. Bit 7 is a continuation bit. See write_varinum() for more information.

Returns

Returns the accumulated values as a single number.

12.43.3.17 void seq64::midifile::write_long (midilong *x*) [private]

Warning

This code looks endian-dependent.

Parameters

x	The long value to be written to the MIDI file.

12.43.3.18 void seq64::midifile::write_short (midishort *x*) [private]

Warning

This code looks endian-dependent.

Parameters

x	The short value to be written to the MIDI file.

12.43.3.19 void seq64::midifile::read_byte_array (midibyte * *b*, int *len*) [inline], [private]

Parameters

b	The byte array to receive the data.
len	The number of bytes in the array, and to be read.

12.43.3.20 void seq64::midifile::write_byte (midibyte *c*) [inline], [private]

The byte is written to the m_char_list member, using a call to push_back().

Parameters

c	The MIDI byte to be "written".

12.43.3.21 void seq64::midifile::write_varinum (midilong *value*) [private]

A MIDI file Variable Length Value is stored in bytes. Each byte has two parts: 7 bits of data and 1 continuation bit. The highest-order bit is set to 1 if there is another byte of the number to follow. The highest-order bit is set to 0 if this byte is the last byte in the VLV.

To recreate a number represented by a VLV, first you remove the continuation bit and then concatenate the leftover bits into a single number.

To generate a VLV from a given number, break the number up into 7 bit units and then apply the correct continuation bit to each byte.

In theory, you could have a very long VLV number which was quite large; however, in the standard MIDI file specification, the maximum length of a VLV value is 5 bytes, and the number it represents can not be larger than 4 bytes.

Here are some common cases:

```
-  Numbers between 0 and 127 (0x7F) are represented by a single
   byte.
-  0x80 is represented as "0x81 0x00".
-  0x0FFFFFFF (the largest number) is represented as "0xFF 0xFF
   0xFF 0x7F".
```

Also see the varinum_size() function.

Parameters

value	The long value to be encoded as a MIDI varinum, and written to the MIDI file.

12.43.3.22 void seq64::midifile::write_track_name (const std::string & *trackname*) [private]

Note that we have to precede this "event" with a delta time value, set to 0. The format of the output is "0x00 0xFF 0x03 len track-name-bytes".

Parameters

trackname	Provides the name of the track to be written to the MIDI file.

12.43.3.23 std::string seq64::midifile::read_track_name ( ) [private]

Meant only for usage in the proprietary/SeqSpec footer track, in the new file format.

Returns

Returns the track name, or an empty string if there was a problem.

12.43.3.24 void seq64::midifile::write_seq_number (midishort *seqnum*) [private]

The format is "00 FF 00 02 ss ss", where "02" is actually the constant length of the data. We have to precede these values with a 0 delta time, of course.

Now, for sequence 0, an alternate format is "FF 00 00". But that format can only occur in the first track, and the rest of the tracks then don't need a sequence number, since it is assumed to increment. Our application doesn't bother with that shortcut.

Parameters

seqnum	The sequence number to write.

12.43.3.25 int seq64::midifile::read_seq_number ( ) [private]

Meant only for usage in the proprietary/SeqSpec footer track, in the new file format.

Returns

Returns the sequence number found, or -1 if it was not found.

12.43.3.26 void seq64::midifile::write_track_end ( ) [private]

12.43.3.27 void seq64::midifile::write_prop_header (midilong *control_tag*, long *data_length*) [private]

- 0x4D54726B. The track tag "MTrk". The MIDI spec requires that software can skip over non-standard chunks. "Prop"? Would require a fix to midicvt.
- 0xaabbccdd. The length of the track. This needs to be calculated somehow.
- 0x00. A zero delta time.
- 0x7f7f. Sequence number, a special value, well out of normal range.
- The name of the track:
  - "Seq24-Spec"
  - "Sequencer64-S"

Then follows the proprietary/SeqSpec data, written in the normal manner. Finally, tack on the track-end meta-event.
Components of final track size:

```
-# Delta time.  1 byte, always 0x00.
-# Sequence number.  5 bytes.  OPTIONAL.  We won't write it.
-# Track name. 3 + 10 or 3 + 15
-# Series of proprietary/SeqSpec specs:
   -# Prop header:
      -# If legacy format, 4 bytes.
      -# Otherwise, 2 bytes + varinum_size(length) + 4 bytes.
      -# Length of the prop data.
-# Track End. 3 bytes.
```

Writes a "proprietary" (SeqSpec) Seq24 footer header in either the new MIDI-compliant format, or the legacy Seq24 format. This function does not write the data. It replaces calls such as "write_long(c_midich)" in the proprietary secton of write().

The legacy format just writes the control tag (0x242400xx). The new format writes 0x00 0xFF 0x7F len 0x242400xx; the first 0x00 is the delta time.

In the new format, the 0x24 is a kind of "manufacturer ID". At http://www.midi.org/techspecs/manid.↩
php we see that most manufacturer IDs start with 0x00, and are thus three bytes long, or start with codes at 0x40 and above. Similary, this site shows that no manufacturer uses 0x24:

```
http://sequence15.blogspot.com/2008/12/midi-manufacturer-ids.html
```

Warning

Currently, the manufacturer ID is not handled; it is part of the data, which can be misleading in programs that analyze MIDI files.

Parameters

control_tag	Determines the type of sequencer-specific section to be written. It should be one of the value in the globals module, such as c_midibus or c_mutegroups.
data_length	The amount of data that will be written. This parameter does not count the length of the header itself.

12.43.3.28 bool seq64::midifile::write_proprietary_track (perform & *p*) [private]

The first thing to do, for the new format only, is calculate the length of this big section of data. This was quite tricky; we tweaked and adjusted until the midicvt program handled the whole new-format file without emitting any errors.

Here's the basics of what Seq24 did for writing the data in this part of the file:

```
-#  Write the c_midictrl value, then write a 0.  To us, this looks like
    no one wrote any code to write this data.  And yet, the parsing
    code can handles a non-zero value, which is the number of sequences
    as a long value, not a byte.  So shouldn't we write 4 bytes, not
    one?  Yes, indeed, we made a mistake.  However, we should be
    writing out the full data set as well.  But not even Seq24 does
    that!  Perhaps they decided it was best kept in the "rc"
    configuration file.
-#  MORE TO COME.
```

Parameters

p	Provides the object that will contain and manage the entire performance.

Returns

Always returns true. No efficient way to check all of the writes that can happen. Might revisit this issue if some bug crops up.

12.43.3.29 long seq64::midifile::varinum_size (long *len*) const [private]

This function is needed when calculating the length of a track. Note that it handles only the following situations:

```
https://en.wikipedia.org/wiki/Variable-length_quantity
```

This restriction allows the calculation to be simple and fast.

```
1 byte:  0x00 to 0x7F
2 bytes: 0x80 to 0x3FFF
3 bytes: 0x4000 to 0x001FFFFF
4 bytes: 0x200000 to 0x0FFFFFFF
```

Parameters

len	The long value whose length, when encoded as a MIDI varinum, is to be found.

Returns

Returns values as noted above. Anything beyond that range returns 0.

12.43.3.30 long seq64::midifile::prop_item_size (long *data_length*) const [private]

If using the new format, the length includes the sum of sequencer-specific tag (0xFF 0x7F) and the size of the variable-length value. Then, for legacy and new format, 4 bytes are added for the Seq24 MIDI control value, and then the data length is added.

Parameters

data_length	Provides the data length value to be encoded.

Returns

Returns the length of the item size, including the delta time, meta bytes, length byes, the control tag, and the data-length itself.

12.43.3.31 long seq64::midifile::track_name_size (const std::string & *trackname*) const [private]

Parameters

trackname	Provides the name of the track to be written to the MIDI file.

Returns

Returns the length of the event, which is of the format "0x00 0xFF 0x03 len track-name-bytes".

12.43.3.32 void seq64::midifile::errdump (const std::string & *msg*) [private]

It adds the file offset to the message.

Parameters

msg	The main error message string, without an ending newline character.

Returns

The constructed string is returned as a side-effect, in case we want to pass it along to the externally-accessible error-message buffer.

12.43.3.33 void seq64::midifile::errdump (const std::string & *msg,* unsigned long *value*) [private]

It adds the file offset to the message.

Parameters

msg	The main error message string, without an ending newline character.
value	The long value to show as part of the message.

Returns

The constructed string is returned as a side-effect, in case we want to pass it along to the externally-accessible error-message buffer.

12.43.3.34 long seq64::midifile::seq_number_size ( ) const [inline], [private]

12.43.3.35 long seq64::midifile::track_end_size ( ) const [inline], [private]

12.43.3.36 bool seq64::midifile::is_sysex_special_id (midibyte *ch*) [inline], [private]

Parameters

ch	Provides the byte to be checked against 0x7D through 0x7F.

Returns

Returns true if the byte is SysEx special ID.

12.43.4 Field Documentation

12.43.4.1 int seq64::midifile::m_file_size [private]

This variable was added when loading a file that caused an attempt to load data well beyond the file-size of the midicvt test file Dixie04.mid.

12.43.4.2 std::string seq64::midifile::m_error_message [private]

If empty, there's no pending error. Currently most useful in the parse() function.

12.43.4.3 bool seq64::midifile::m_error_is_fatal [private]

The caller can query for this value after getting the return value from parse().

12.43.4.4 bool seq64::midifile::m_disable_reported [private]

Once is enough.

12.43.4.5 int seq64::midifile::m_pos [private]

This is at least a 31-bit value in the recent architectures running Linux and Windows, so it will handle up to 2 Gb of data. This member is used as the offset into the m_data vector.

12.43.4.6 const std::string seq64::midifile::m_name [private]

12.43.4.7 std::vector<midibyte> seq64::midifile::m_data [private]

We could also use a string of characters, unsigned. This member is resized to the putative size of the MIDI file, in the parse() function. Then the whole file is read into it, as if it were an array. This member is an input buffer.

12.43.4.8 std::list<midibyte> seq64::midifile::m_char_list [private]

The class pushes each MIDI byte into this list using the write_byte() function. Also note that the write() function calls sequence::fill_list() to fill a temporary std::list<char> (!) buffer, then writes that data *backwards* to this member. This member is an output buffer.

12.43.4.9 bool seq64::midifile::m_new_format [private]

In the new format, each sequencer-specfic value (0x242400xx, as defined in the globals module) is preceded by the sequencer-specific prefix, 0xFF 0x7F len id/date). By default, the new format is used, but the user can specify the –legacy (-l) option, or make a soft link to the sequence24 binary called "seq24", to write the data in the old format. [We will eventually add the –legacy option to the "rc" configuration file.] Note that reading can handle either format transparently.

12.43.4.10 bool seq64::midifile::m_global_bgsequence [private]

12.43.4.11 int seq64::midifile::m_ppqn [private]

12.43.4.12 bool seq64::midifile::m_use_default_ppqn [private]

12.43.4.13 midi_splitter seq64::midifile::m_smf0_splitter [private]

This object holds all of the information needed to split a multi-channel sequence.

12.44 seq64::mutex Class Reference

The mutex class provides a simple wrapper for the pthread_mutex_t type used as a recursive mutex.

Inheritance diagram for seq64::mutex:



Public Member Functions

- mutex ()

  The constructor assigns the recursive mutex to the local locking mutex.
- void lock () const

  Lock the mutex.
- void unlock () const

  Unlock the mutex.

Protected Attributes

- pthread_mutex_t m_mutex_lock

  Provides a mutex lock usable by a single module or class.

Static Private Attributes

- static const pthread_mutex_t sm_recursive_mutex

  Provides a recursive mutex that can be used by the whole application, and is, apparently.

12.44.1 Constructor & Destructor Documentation

12.44.1.1 seq64::mutex::mutex ( )

12.44.2 Member Function Documentation

12.44.2.1 void seq64::mutex::lock ( ) const

12.44.2.2 void seq64::mutex::unlock ( ) const

12.44.3 Field Documentation

12.44.3.1 const pthread_mutex_t seq64::mutex::sm_recursive_mutex [static], [private]

Define the static recursive mutex and its condition variable.

12.44.3.2 pthread_mutex_t seq64::mutex::m_mutex_lock [mutable], [protected]

However, this mutex ends up being a copy of the static sm_recursive_mutex (and, of course, a different "object").

12.45 seq64::editable_event::name_value_t Struct Reference

Provides a type that contains the pair of values needed for the various lookup maps that are needed to manage editable events.

Data Fields

- unsigned short event_value

  Holds a midibyte value (0x00 to 0xFF) or SEQ64_END_OF_MIDIBYTE_TABLE to indicate the end of an array of name_value_t items.
- std::string event_name

  Holds the human-readable name for an event code or other numeric value in an array of name_value_t items.

12.45.1 Field Documentation

12.45.1.1 unsigned short seq64::editable_event::name_value_t::event_value

12.45.1.2 std::string seq64::editable_event::name_value_t::event_name

12.46 seq64::options Class Reference

This class supports a full tabbed options dialog.

Inherits Dialog.

Public Member Functions

- options (Gtk::Window &parent, perform &p)

Private Types

Private Member Functions

- perform & perf ()

  'Getter' function for member m_mainperf
- void clock_callback_off (int bus, Gtk::RadioButton *button)
- void clock_callback_on (int bus, Gtk::RadioButton *button)
- void clock_callback_mod (int bus, Gtk::RadioButton *button)
- void clock_mod_callback (Gtk::Adjustment *adj)
- void input_callback (int bus, Gtk::Button *button)
- void transport_callback (button type, Gtk::Button *button)
- void mouse_seq24_callback (Gtk::RadioButton *)
- void mouse_fruity_callback (Gtk::RadioButton *)
- void mouse_mod4_callback (Gtk::CheckButton *)
- void lash_support_callback (Gtk::CheckButton *)
- void add_midi_clock_page ()
- void add_midi_input_page ()
- void add_keyboard_page ()
- void add_mouse_page ()
- void add_jack_sync_page ()

Private Attributes

- Gtk::Tooltips * m_tooltips

  A repository for GTK tooltip support.
- perform & m_mainperf

  The performance object to which some of these options apply.
- Gtk::Button * m_button_ok

  The famous "OK" button's pointer.
- Gtk::CheckButton * m_button_jack_transport

  Main JACK transport selection.
- Gtk::CheckButton * m_button_jack_master

  Main JACK transport master selection.
- Gtk::CheckButton * m_button_jack_master_cond

  Main JACK transport master-conditional selection.
- Gtk::Button * m_button_jack_connect

  JACK Connect button, which we need to enable/disable for clarity and some additional safety.
- Gtk::Button * m_button_jack_disconnect

  JACK Disonnect button, which we need to enable/disable for clarity and some additional safety.
- Gtk::Notebook * m_notebook

  Not sure yet what this notebook is for.

12.46.1 Member Enumeration Documentation

12.46.1.1 enum seq64::options::button [private]

These values are handled in options::transport_callback(). Some of them set JACK-related values in the rc_settings object, while the others set up or tear down the JACK support of sequencer64.

The JACK Transport settings are a little messy. They should be radio buttons, and control each other's settings. Currently, if the user wants to set up for JACK Master, the JACK Transport button must also be checked.

Enumerator

e_jack_transport Turns on the "with JACK Transport" option, rc_settings::with_jack_transport().

e_jack_master Turns on the "with JACK Master" option, rc_settings::with_jack_master(). If another application is already JACK Master, this will fail.

e_jack_master_cond Turns on the "with JACK Master" option rc_settings::with_jack_master_cond(). This option makes sequencer64 the JACK Master conditionally, that is, if no other application has claimed that role.

e_jack_start_mode_live Doesn't directly do anything; the live mode versus song mode is set by the e_↩ jack_start_mode_song value.

e_jack_start_mode_song Sets the "JACK start mode" value to true, which means that sequencer64 is in song mode. This value is obtained via rc_settings::jack_start_mode().

e_jack_connect Causes the perform object's JACK initialization function, perform::init_jack(), to be called.

e_jack_disconnect Causes the perform object's JACK deinitialization function, perform::deinit_jack(), to be called.

12.46.2 Constructor & Destructor Documentation

12.46.2.1 seq64::options::options (Gtk::Window & *parent,* perform & *p*)

12.46.3 Member Function Documentation

12.46.3.1 perform& seq64::options::perf ( ) [inline], [private]

12.46.3.2 void seq64::options::clock_callback_off (int *bus,* Gtk::RadioButton * *button*) [private]

12.46.3.3 void seq64::options::clock_callback_on (int *bus,* Gtk::RadioButton * *button*) [private]

12.46.3.4 void seq64::options::clock_callback_mod (int *bus,* Gtk::RadioButton * *button*) [private]

12.46.3.5 void seq64::options::clock_mod_callback (Gtk::Adjustment * *adj*) [private]

12.46.3.6 void seq64::options::input_callback (int *bus,* Gtk::Button * *button*) [private]

12.46.3.7 void seq64::options::transport_callback (button *type,* Gtk::Button * *button*) [private]

12.46.3.8 void seq64::options::mouse_seq24_callback (Gtk::RadioButton *) [private]

12.46.3.9 void seq64::options::mouse_fruity_callback (Gtk::RadioButton *) [private]

12.46.3.10 void seq64::options::mouse_mod4_callback (Gtk::CheckButton *) [private]

12.46.3.11 void seq64::options::lash_support_callback (Gtk::CheckButton *) [private]

12.46.3.12 void seq64::options::add_midi_clock_page ( ) [private]

12.46.3.13 void seq64::options::add_midi_input_page ( ) [private]

12.46.3.14 void seq64::options::add_keyboard_page ( ) [private]

12.46.3.15 void seq64::options::add_mouse_page ( ) [private]

12.46.3.16 void seq64::options::add_jack_sync_page ( ) [private]

12.46.4 Field Documentation

12.46.4.1 Gtk::Tooltips* seq64::options::m_tooltips [private]

12.46.4.2 perform& seq64::options::m_mainperf [private]

12.46.4.3 Gtk::Button* seq64::options::m_button_ok [private]

12.46.4.4 Gtk::CheckButton* seq64::options::m_button_jack_transport [private]

12.46.4.5 Gtk::CheckButton* seq64::options::m_button_jack_master [private]

12.46.4.6 Gtk::CheckButton* seq64::options::m_button_jack_master_cond [private]

12.46.4.7 Gtk::Button* seq64::options::m_button_jack_connect [private]

12.46.4.8 Gtk::Button* seq64::options::m_button_jack_disconnect [private]

12.46.4.9 Gtk::Notebook* seq64::options::m_notebook [private]

Must be a GTK thang.

12.47 seq64::optionsfile Class Reference

Provides a file for reading and writing the application' main configuration file.

Inheritance diagram for seq64::optionsfile:



Public Member Functions

- optionsfile (const std::string &name)

  Principal constructor.
- ~optionsfile ()

  A rote destructor.
- bool parse (perform &perf)

  Parse the ~/.seq24rc or ~/.config/sequencer64/sequencer64.rc file.
- bool write (const perform &perf)

  This options-writing function is just about as complex as the options-reading function.

Private Member Functions

- bool error_message (const std::string &sectionname)

  Helper function for error-handling.

Additional Inherited Members

12.47.1 Detailed Description

The settings that are passed around are provided or used by the perform class.

12.47.2 Constructor & Destructor Documentation

12.47.2.1 seq64::optionsfile::optionsfile (const std::string & *name*)

Parameters

name	Provides the name of the options file; this is usually a full path file-specification.

12.47.2.2 seq64::optionsfile::~optionsfile ( )

12.47.3 Member Function Documentation

12.47.3.1 bool seq64::optionsfile::parse (perform & *p*) [virtual]

[midi-control]

Get the number of sequence definitions provided in the [midi-control] section. Ranges from 32 on up. Then read in all of the sequence lines. The first 32 apply to the first screen set. There can also be a comment line "# mute in group" followed by 32 more lines. Then there are addditional comments and single lines for BPM up, BPM down, Screen Set Up, Screen Set Down, Mod Replace, Mod Snapshot, Mod Queue, Mod Gmute, Mod Glearn, and Screen Set Play. These are all forms of MIDI automation useful to control the playback while not sitting near the computer.

[mute-group]

The mute-group starts with a line that indicates up to 32 mute-groups are defined. A common value is 1024, which means there are 32 groups times 32 keys. But this value is currently thrown away. This value is followed by 32 lines of data, each contained 4 sets of 8 settings. See the seq24-doc project on GitHub for a much more detailed description of this section.

[midi-clock]

The MIDI-clock section defines the clocking value for up to 16 output busses. The first number, 16, indicates how many busses are specified. Generally, these busses are shown to the user with names such as "[1] seq24 1".

[keyboard-control]

The keyboard control defines the keys that will toggle the stage of each of up to 32 patterns in a pattern/sequence box. These keys are displayed in each box as a reminder. The first number specifies the Key number, and the second number specifies the Sequence number.

[keyboard-group]

The keyboard group specifies more automation for the application. The first number specifies the Key number, and the second number specifies the Group number. This section should be better described in the seq24-doc project on GitHub.

[jack-transport]

This section covers various JACK settings, one setting per line. In order, the following numbers are specfied:

```
-   jack_transport - Enable sync with JACK Transport.
-   jack_master - Seq24 will attempt to serve as JACK Master.
-   jack_master_cond - Seq24 will fail to be Master if there is
    already a Master set.
-   jack_start_mode:
    -   0 = Playback will be in Live mode.  Use this to allow
        muting and unmuting of loops.
    -   1 = Playback will use the Song Editor's data.
```

[midi-input]

This section covers the MIDI input busses, and has a format similar to "[midi-clock]". Generally, these busses are shown to the user with names such as "[1] seq24 1", and currently there is only one input buss. The first field is the port number, and the second number indicates whether it is disabled (0), or enabled (1).

[midi-clock-mod-ticks]

This section covers.... One common value is 64.

[manual-alsa-ports]

This section covers.... Set to 1 if you want seq24 to create its own ALSA ports and not connect to other clients.

[last-used-dir]

This section simply holds the last path-name that was used to read or write a MIDI file. We still need to add a check for a valid path, and currently the path must start with a "/", so it is not suitable for Windows.

[interaction-method]

This section specified the kind of mouse interaction.

- 0 = 'seq24' (original Seq24 method).
- 1 = 'fruity' (similar to a certain fruity sequencer we like).

The second data line is set to "1" if Mod4 can be used to keep seq24 in note-adding mode even after the right-click is released, and "0" otherwise.

Parameters

p	Provides the performance object to which all of these options apply.

Returns

Returns true if the file was able to be opened for reading. Currently, there is no indication if the parsing actually succeeded.

Implements seq64::configfile.

12.47.3.2 bool seq64::optionsfile::write (const perform & *p*) [virtual]

Parameters

p	Provides a const reference to the main perform object. However, we have to cast away the constness, because too many of the perform getter functions are used in non-const contexts.

Returns

Returns true if the write operations all succeeded.

New boolean to show sequence numbers; ignored in legacy mode.

Implements seq64::configfile.

12.47.3.3 bool seq64::optionsfile::error_message (const std::string & *sectionname*) [private]

Parameters

sectionname	Provides the name of the section for reporting the error.

Returns

Always returns false.

12.48 seq64::perfedit Class Reference

This class supports a Performance Editor that is used to arrange the patterns/sequences defined in the patterns panel.

Inheritance diagram for seq64::perfedit:



Public Member Functions

- perfedit (perform &p, bool second_perfedit=false, int ppqn=SEQ64_USE_DEFAULT_PPQN)

  Principal constructor, has a reference to a perform object.
- virtual ~perfedit ()

  This rote constructor does nothing.
- void init_before_show ()

This function forwards its call to the perfroll function of the same name.

- void enqueue_draw (bool forward=true)

  Helper wrapper for calling perfroll::queue_draw() for one or both perfedits.
- void enregister_peer (perfedit *peer)

  Register the peer perfedit object.
- void set_zoom (int z)

  Implements the horizontal zoom feature.

Static Public Member Functions

- static bool zoom_check (int z)

  Checks zoom values for the z/Z keystrokes used in perfroll and perftime.

Private Member Functions

- void set_beats_per_bar (int bpm)

  Sets the beats-per-measure text and value to the given value, and then calls set_guides().
- void set_beat_width (int bw)

  Sets the BW (beat width, or the denominator in the time signature) text and values to the given value, and then calls set_guides().
- void set_snap (int snap)

  Sets the snap text and values to the given value, and then calls set_guides().
- void set_guides ()

  Sets the guides, which are the L and R user-interface elements.
- void grow ()

  Increments the size of the perfroll and perftime objects.
- void set_looped ()

  Set the looping in the perform object.
- void expand ()

  Implement the expand action.
- void collapse ()

  Implement the collapse action.
- void copy ()

  Implement the copy (actually, expand-and-copy) action.
- void undo ()

  Implement the undo feature (Ctrl-Z).
- void popup_menu (Gtk::Menu *menu)

  Opens the given popup menu.
- void draw_sequences ()

  Forces a redraw of the sequences, though currently just the perfnames part of each sequence in the performance editor.
- bool timeout ()

  Handles a drawing timeout.
- void set_image (bool isrunning)

  Changes the image used for the pause/play button.
- void start_playing ()

  Implement the playing.
- void pause_playing ()

  Pauses the playing of the song, leaving the progress bar where it stopped.
- void stop_playing ()

Stop the playing.

- void toggle_playing ()

  Reverses the state of playback.

- void on_realize ()

  This callback function calls the base-class on_realize() function, and then connects the perfedit::timeout() function to the Glib signal-timeout, with a redraw timeout of redraw_period_ms().

- bool on_key_press_event (GdkEventKey *ev)

  This function is the callback for a key-press event.

- bool on_delete_event (GdkEventAny *)

  All this callback function does is return false.

Private Attributes

- perfedit * m_peer_perfedit

  The partner instance of perfedit.

- Gtk::Table * m_table

  A whole horde of GUI elements.

- Gtk::Adjustment * m_vadjust

  Vertical adjust for piano roll.

- Gtk::Adjustment * m_hadjust

  Horizontal adjust for piano roll.

- Gtk::VScrollbar * m_vscroll

  Vertical scroll for piano roll.

- Gtk::HScrollbar * m_hscroll

  Horizonatl scroll for piano roll.

- perfnames * m_perfnames

  Pattern names in leftmost column.

- perfroll * m_perfroll

  The piano roll in the song editor.

- perftime * m_perftime

  The time/measures bar above roll.

- Gtk::Menu * m_menu_snap

  The menu for grid-snap selection.

- Gtk::Image * m_image_play

  The image for the play button.

- Gtk::Button * m_button_snap

  Button to bring up the snap menu.

- Gtk::Entry * m_entry_snap

  Text edit for the grid-snap value.

- Gtk::Button * m_button_stop

  The Stop Play button object.

- Gtk::Button * m_button_play

  Implements the yellow two-bar pause button.

- Gtk::ToggleButton * m_button_loop

  Button for Left-to-Right looping.

- Gtk::Button * m_button_expand

  Button for Left/Right expansion.

- Gtk::Button * m_button_collapse

  Button for Left/Right collapse.

- Gtk::Button * m_button_copy

Expand and copy between L/R.

- Gtk::Button * m_button_grow

  Expand grid (bottom-right button).

- Gtk::Button * m_button_undo

  Button to undo previous action.

- Gtk::Button * m_button_bpm

  Beats-per-measure menu button.

- Gtk::Entry * m_entry_bpm

  Text-edit for beats-per-measure.

- Gtk::Button * m_button_bw

  Beat-width menu button.

- Gtk::Entry * m_entry_bw

  Text-edit for beat-width.

- Gtk::HBox * m_hbox

  Horizontal box (which?) in table.

- Gtk::HBox * m_hlbox

  Horizontal box for buttons at top.

- Gtk::Tooltips * m_tooltips

  Container for tool-tips.

- Gtk::Menu * m_menu_bpm

  Menus for time signature, beats per measure, beat width.

- Gtk::Menu * m_menu_bw

  Drop-down menu for beat-width.

- int m_snap

  Sets the horizontal grid snap-to in units of "pulses" or "ticks".

- int m_bpm

  The current "beats per measure" value.

- int m_bw

  The current "beat width" value.

- int m_ppqn

  The current "parts per quarter note" value.

- bool m_is_running

  Holds the current status of running, for use in display the play versus pause icon.

- int m_standard_bpm

  The standard "beats per measure" of Sequencer64, which here matches the beats-per-measure displayed in the perfroll (piano roll).

Friends

- void update_perfedit_sequences ()

  This global function in the seq64 namespace calls perfedit :: draw_sequences(), if the global perfedit objects exist.

Additional Inherited Members

12.48.1 Detailed Description

It has a seqroll and piano roll? No, it has a perform, a perfnames, a perfroll, and a perftime.

12.48.2 Constructor & Destructor Documentation

12.48.2.1 seq64::perfedit::perfedit (perform & *p*, bool *second_perfedit* = `false`, int *ppqn* = `SEQ64_USE_DEFAULT_PPQN`)

We've reordered the pointer members and put them in the initializer list to make the constructor a bit cleaner.

Todo Offload most of the work into an initialization function like options does.

Parameters

p	Refers to the main performance object.
second_perfedit	If true, this object is the second perfedit object.
ppqn	The optionally-changed PPQN value to use for the performance editor.

12.48.2.2 seq64::perfedit::~perfedit ( ) [virtual]

We're going to have to run the application through valgrind to make sure that nothing is left behind.

12.48.3 Member Function Documentation

12.48.3.1 void seq64::perfedit::init_before_show ( )

It does not seem to need to also forward to the perftime function of the same name.

12.48.3.2 void seq64::perfedit::enqueue_draw (bool *forward* = `true`)

Note that we call the children's queue_draw() functions, not enqueue_draw(), otherwise we'll get stack overflow.

Parameters

forward	If true (the default), pass the call to the peer. When passing this call to the peer, this parameter is set to false to prevent an infinite loop and the resultant stack overflow.

12.48.3.3 static bool seq64::perfedit::zoom_check (int *z*) [inline], [static]

It has to range from greater than 1 (the highest zoom-in causes an unexplained drawing artifact at this time), and not greater than four times the c_perf_scale_x value, at which point we have zoomed out so far that the measure numbers are almost completely obscured.

Parameters

z	The desired zoom value to validate.

12.48.3.4 void seq64::perfedit::enregister_peer (perfedit * peer) [inline]

This function is meant to be called by mainwnd, which creates the perfedits and then makes sure they get along. Only the first call to this function will work; only one peer can be registered.

Parameters

peer	The peer perfedit object to register, if not null.

12.48.3.5 void seq64::perfedit::set_zoom (int z)

12.48.3.6 void seq64::perfedit::set_beats_per_bar (int bpm) [private]

The usage of is modified was faulty. Offloaded it to the perform object to make it more foolproof. See the perform::modify() function.

Parameters

bpm	Provides the beats/measure or beats/bar value to be set. This value is basically the numerator of the time signature.

12.48.3.7 void seq64::perfedit::set_beat_width (int bw) [private]

The usage of is modified was faulty. Offloaded it to the perform object to make it more foolproof. See the perform::modify() function.

Parameters

bw	Provides the beat width to be set. The beat width is basically the denominator of the time signature.

12.48.3.8 void seq64::perfedit::set_snap (int snap) [private]

Parameters

snap	Provide the snap value to be set. This value is basically the numerator of the expression "1 / snap".

12.48.3.9 void seq64::perfedit::set_guides ( ) [private]

See the set_snap() function.

It's a little confusing; I assigned the label "m_standard_bpm" to the value 4 in "measure_pulse = 192 * 4 * m_bpm / m_bw", but I am not sure I understand this equation... why the extra factor of 4? That 4 appears in "c_ppqn * 4" a lot in the original code.

12.48.3.10 void seq64::perfedit::grow ( ) [private]

Make sure that setting the modified flag makes sense for this operation. It doesn't seem to modify members.

12.48.3.11 void seq64::perfedit::set_looped ( ) [private]

12.48.3.12 void seq64::perfedit::expand ( ) [private]

This action opens up a space of events between the L and R (left and right) markers. This action is preceded by pushing an Undo operation in the perform object, moving its triggers, and telling the perfroll to redraw.

12.48.3.13 void seq64::perfedit::collapse ( ) [private]

This action removes all events between the L and R (left and right) markers. This action is preceded by pushing an Undo operation in the perform object, not moving its triggers (they go away), and telling the perfroll to redraw.

12.48.3.14 void seq64::perfedit::copy ( ) [private]

This action opens up a space of events between the L and R (left and right) markers, and copies the information from the same amount of events that follow the R marker. This action is preceded by pushing an Undo operation in the perform object, copying its triggers, and telling the perfroll to redraw.

12.48.3.15 void seq64::perfedit::undo ( ) [private]

We pop an Undo trigger, and then ask the perfroll to queue up a (re)drawing action.

12.48.3.16 void seq64::perfedit::popup_menu (Gtk::Menu * *menu*) [private]

12.48.3.17 void seq64::perfedit::draw_sequences ( ) [private]

This is meant to be called when the focus of an open seqedit or eventedit window changes.

12.48.3.18 bool seq64::perfedit::timeout ( ) [private]

It redraws "dirty" sequences in the perfroll and the perfnames objects, and shows draw progress on the perfroll. It also changes the pause/play image if the status of running has changed. This function is called frequently and continuously. It will work for both perfedit windows, if both are up.

12.48.3.19 void seq64::perfedit::set_image (bool *isrunning*) [private]

Parameters

isrunning	If true, the image should be the pause image. Otherwise, it should be the play image.

12.48.3.20 void seq64::perfedit::start_playing ( ) [private]

JACK will be used if it is present and, in the application, enabled and working.

12.48.3.21 void seq64::perfedit::pause_playing ( ) [private]

Currently, it is just the same as stop_playing(), but we will get it to work. Keeps the stop button enabled as a kind of rewind for ALSA.

12.48.3.22 void seq64::perfedit::stop_playing ( ) [private]

We need to make the progress line move back to the beginning right away here.

12.48.3.23 void seq64::perfedit::toggle_playing ( ) [inline], [private]

Meant only to be called when the "Play" button is pressed. Currently, the GUI does not change. This function will ultimately act like a Pause/Play button, but currently the pause functionality on works (partially) for JACK transport. Currently not used.

12.48.3.24 void seq64::perfedit::on_realize ( ) [private]

12.48.3.25 bool seq64::perfedit::on_key_press_event (GdkEventKey * *ev*) [private]

By default, the space-bar starts the playing, and the Escape key stops the playing. The start/end key may be the same key (i.e. space-bar), allow toggling when the same key is mapped to both triggers. Note that we now pass false in the call to perform::playback_key_event(), if SEQ64_PAUSE_SUPPORT is compiled in. Song mode doesn't yield the pause effect we want.

Parameters

ev	Provides the key event to implement.

12.48.3.26 bool seq64::perfedit::on_delete_event (GdkEventAny *) [inline], [private]

12.48.4 Friends And Related Function Documentation

12.48.4.1 void update_perfedit_sequences ( ) [friend]

It is used by other objects (seqedit and eventedit) that can modify the currently-edited sequence shown in the perfedit (song window).

12.48.5 Field Documentation

12.48.5.1 perfedit* seq64::perfedit::m_peer_perfedit [private]

12.48.5.2 Gtk::Table* seq64::perfedit::m_table [private]

Layout table for song editor.

12.48.5.3 Gtk::Adjustment* seq64::perfedit::m_vadjust [private]

12.48.5.4 Gtk::Adjustment* seq64::perfedit::m_hadjust [private]

12.48.5.5 Gtk::VScrollbar* seq64::perfedit::m_vscroll [private]

12.48.5.6 Gtk::HScrollbar* seq64::perfedit::m_hscroll [private]

12.48.5.7 perfnames* seq64::perfedit::m_perfnames [private]

12.48.5.8 perfroll* seq64::perfedit::m_perfroll [private]

12.48.5.9 perftime* seq64::perfedit::m_perftime [private]

12.48.5.10 Gtk::Menu* seq64::perfedit::m_menu_snap [private]

12.48.5.11 Gtk::Image* seq64::perfedit::m_image_play [private]

12.48.5.12 Gtk::Button* seq64::perfedit::m_button_snap [private]

12.48.5.13 Gtk::Entry* seq64::perfedit::m_entry_snap [private]

12.48.5.14 Gtk::Button* seq64::perfedit::m_button_stop [private]

12.48.5.15 Gtk::Button* seq64::perfedit::m_button_play [private]

The Play button object.

12.48.5.16 Gtk::ToggleButton* seq64::perfedit::m_button_loop [private]

12.48.5.17 Gtk::Button* seq64::perfedit::m_button_expand [private]

12.48.5.18 Gtk::Button* seq64::perfedit::m_button_collapse [private]

12.48.5.19 Gtk::Button* seq64::perfedit::m_button_copy [private]

12.48.5.20 Gtk::Button* seq64::perfedit::m_button_grow [private]

12.48.5.21 Gtk::Button* seq64::perfedit::m_button_undo [private]

12.48.5.22 Gtk::Button* seq64::perfedit::m_button_bpm [private]

12.48.5.23 Gtk::Entry* seq64::perfedit::m_entry_bpm [private]

12.48.5.24 Gtk::Button* seq64::perfedit::m_button_bw [private]

12.48.5.25 Gtk::Entry* seq64::perfedit::m_entry_bw [private]

12.48.5.26 Gtk::HBox* seq64::perfedit::m_hbox [private]

12.48.5.27 Gtk::HBox* seq64::perfedit::m_hlbox [private]

12.48.5.28 Gtk::Tooltips* seq64::perfedit::m_tooltips [private]

12.48.5.29 Gtk::Menu* seq64::perfedit::m_menu_bpm [private]

Drop-down menu for beats/minute.

12.48.5.30 Gtk::Menu* seq64::perfedit::m_menu_bw [private]

12.48.5.31 int seq64::perfedit::m_snap [private]

12.48.5.32 int seq64::perfedit::m_bpm [private]

Do not confuse it with BPM (beats per minute). The numerator of the time signature.

12.48.5.33 int seq64::perfedit::m_bw [private]

The denominator of the time signature.

12.48.5.34 int seq64::perfedit::m_ppqn [private]

12.48.5.35 bool seq64::perfedit::m_is_running [private]

12.48.5.36 int seq64::perfedit::m_standard_bpm [private]

12.49 seq64::perfnames Class Reference

This class implements the left-side keyboard in the patterns window.

Inheritance diagram for seq64::perfnames:



Public Member Functions

- perfnames (perform &p, perfedit &parent, Gtk::Adjustment &vadjust)

  Principal constructor for this user-interface object.
- virtual ~perfnames ()

  Let's provide a do-nothing virtual destructor.
- void redraw_dirty_sequences ()

  Redraws sequences that have been modified.

Private Member Functions

- void enqueue_draw ()

  Wraps queue_draw() and forwards the call to the parent perfedit, so that it can forward it to any other perfedit that exists, and to the other sub-elements of the song editor.
- int convert_y (int y)

  Converts a y-value into a sequence number and returns it.
- void draw_sequences ()

  New function to encapsulate forced redrawing of all sequence names in the current viewport.
- void draw_sequence (int sequence)

  Draw the given sequence.
- void change_vert ()

  Change the vertial offset of a sequence/pattern.
- void redraw (int sequence)

  Redraw the given sequence.
- void on_realize ()

  Handles the callback when the window is realized.
- bool on_expose_event (GdkEventExpose *ev)

  Handles an on-expose event.
- bool on_button_press_event (GdkEventButton *ev)

  Provides the callback for a button press, and it handles only a left mouse button [the right mouse button is handled in on_button_release_event()].
- bool on_button_release_event (GdkEventButton *ev)

  Handles a button-release for the right button, bringing up a popup menu that is identical to the right-click popup menu for a slot in the patterns panel (mainwid), and context sensitive.
- void on_size_allocate (Gtk::Allocation &)

  Handles a size-allocation event.
- bool on_scroll_event (GdkEventScroll *ev)

  Handle the vertical scrolling of the window.

Private Attributes

- perfedit & m_parent

  Provides a link to the perfedit that created this object.
- int m_names_chars

  Provides the number of the characters in the name box.
- int m_char_w

  Provides the "real" width of a character.
- int m_setbox_w

  Provides the width of the "set number" box.
- int m_namebox_w

Provides the width of the "name" box.

- int m_names_x

  Provides the width of the names box, which is the width of a character for 24 characters.

- int m_names_y

  Provides the height of the names box, which is hardwired to 24 pixels.

- int m_xy_offset

  Provides the horizontal and vertical offsets of the text relative to the names box.

- const int m_seqs_in_set

  The number of sequences in a set, currently still hardwired to 32.

- const int m_sequence_max

  The maximum number of sequences, current 32 x 32 = 1024.

- int m_sequence_offset

  The offset from the 0th sequence, which is determined by the vertical view of the piano roll, controlled by the vertical scroll-bar.

- bool m_sequence_active [c_max_sequence]

  Indicates if the given sequence is active or not.

Friends

- class perfedit

Additional Inherited Members

12.49.1 Detailed Description

It inherits from gui_drawingarea_gtk2 to support the font, color, and other GUI functionality, and from seqmenu to support the right-click Edit/New/Cut right-click menu.

Obsolete Note the usage of virtual base classes. Since these can add some extra overhead, we should determine if we can do without the virtuality (and indeed it doesn't seem to be needed).

12.49.2 Constructor & Destructor Documentation

12.49.2.1 seq64::perfnames::perfnames (perform & *p*, perfedit & *parent*, Gtk::Adjustment & *vadjust*)

Weird is that the window (x,y) are set to (c_names_x, 100), when c_names_y is 22 (now 24) in globals.h.

Parameters

p	Provides a reference to the main performance object of the application.
parent	Provides a reference to the object that contains this object, so that this object can tell the parent to queue up a drawing operation.
vadjust	Provides the vertical scrollbar object needed so that perfnames can respond to scrollbar cursor/thumb movement.

12.49.2.2 virtual seq64::perfnames::~perfnames ( ) [inline], [virtual]

12.49.3 Member Function Documentation

12.49.3.1 void seq64::perfnames::redraw_dirty_sequences ( )

12.49.3.2 void seq64::perfnames::enqueue_draw ( ) [private]

The parent perfedit will call perfnames::queue_draw() on behalf of this object, and it will pass a perfnames::enqueue_draw() to the peer perfedit's perfnames, if the peer exists.

12.49.3.3 int seq64::perfnames::convert_y (int *y*) [private]

Used in figuring out which sequence to mute/unmute in the performance editor.

Parameters

y	The y value (within the vertical limits of the perfnames column to the left of the performance editor's piano roll.

Returns

Returns the sequence number corresponding to the y value.

12.49.3.4 void seq64::perfnames::draw_sequences ( ) [private]

12.49.3.5 void seq64::perfnames::draw_sequence (int *seqnum*) [private]

This function has to be prepared to handle an almost endless list of sequences, including unused ones, to draw them all with compatible styles. The sequences are grouped by set-number. The set-number occurs every 32 sequences in the leftmost column of the window.

1. Render the set number, or a blank box, in leftmost column. If the y height of the first draw_rectangle is m_names_y + 1, then we get a black line for the blank tracks, looks ugly.
2. Make sure that the rectangle drawn with the proper background colors for various combinations of muting and highlighting, otherwise just the name is properly colored.
3. Render the column with the name of the sequence. The channel number ranges from 1 to 16, but SMF 0 is indicated on-screen by a channel number of 0. We get the label format from the perform object, for consistency across windows.

Parameters

seqnum	Index to the sequence information to be drawn.

12.49.3.6 void seq64::perfnames::change_vert ( ) [private]

12.49.3.7 void seq64::perfnames::redraw (int *sequence*) [inline], [private], [virtual]

This function is a virtual function of seqmenu that must be overridden in this class.

Parameters

sequence	Provides the number of the sequence to be redrawn.

Implements seq64::seqmenu.

12.49.3.8 void seq64::perfnames::on_realize ( ) [private]

It first calls the base-class version of on_realize(). Then it allocates any additional resources needed.

12.49.3.9 bool seq64::perfnames::on_expose_event (GdkEventExpose * *ev*) [private]

It draws all of the sequences that will be visible.

We could actually optimize this a tiny bit, to save some additions in the for loop.

Parameters

ev	The expose event, not used.

Returns

Always returns true.

12.49.3.10 bool seq64::perfnames::on_button_press_event (GdkEventButton * *ev*) [private]

Two operations are supported by left-clicking on the sequence/track name:

```
-   Normal.  Toggles the mute status of the sequence that is clicked.
-   Shift.  Toggles the mutes status of all other sequences, making
    this operation an easy way to preview a single sequence in the
    performance editor, then bring back the rest of the tracks.
```

Parameters

ev	The mouse button event.

Returns

Always returns true.

12.49.3.11 bool seq64::perfnames::on_button_release_event (GdkEventButton * *p0*) [private]

Parameters

p0	The button event.

Returns

Always returns false.

12.49.3.12 void seq64::perfnames::on_size_allocate (Gtk::Allocation & *a*) [private]

It first calls the base-class version of this function.

Parameters

a	The allocation event. It is passed to the base-class on_size_allocate() function, and then m_window_x and m_window_y are set to the width and height, respectively, of the allocation.

12.49.3.13 bool seq64::perfnames::on_scroll_event (GdkEventScroll * *ev*) [private]

The vertical value is incremented or decremented by the amount of the step increment, and the page is clamped to the new value.

Parameters

ev	The scrolling event.

Returns

Always returns true.

12.49.4 Friends And Related Function Documentation

12.49.4.1 friend class perfedit [friend]

12.49.5 Field Documentation

12.49.5.1 perfedit& seq64::perfnames::m_parent [private]

We want to support two perfedit windows, but the children of perfedit will have to communicate changes requiring a redraw through the parent.

12.49.5.2 int seq64::perfnames::m_names_chars [private]

Pretty much hardwired to 24 at present.

12.49.5.3 int seq64::perfnames::m_char_w [private]

This value is obtained from a font-renderer accessor function.

12.49.5.4 int seq64::perfnames::m_setbox_w [private]

This used to be hardwired to $6 * 2$ (character-width times two).

12.49.5.5 int seq64::perfnames::m_namebox_w [private]

This used to be a weird calculation based on character width.

12.49.5.6 int seq64::perfnames::m_names_x [private]

12.49.5.7 int seq64::perfnames::m_names_y [private]

This value was once 22 pixels, but we need a little extra room for our new font. This extra room is compatible enough with the old font, as well.

12.49.5.8 int seq64::perfnames::m_xy_offset [private]

Currently hardwired.

12.49.5.9 const int seq64::perfnames::m_seqs_in_set [private]

12.49.5.10 const int seq64::perfnames::m_sequence_max [private]

12.49.5.11 int seq64::perfnames::m_sequence_offset [private]

12.49.5.12 bool seq64::perfnames::m_sequence_active[c_max_sequence] [private]

If this really is the true meaning of this value, we ought to get it directly from the sequence if we can.

12.50 seq64::perform Class Reference

This class supports the performance mode.

Public Member Functions

- perform (gui_assistant &mygui, int ppqn=SEQ64_USE_DEFAULT_PPQN)

  This construction initializes a vast number of member variables, some of them public (but we're working on that)!
- ~perform ()

  The destructor sets some running flags to false, signals this condition, then joins the input and output threads if the were launched.
- bool is_modified () const

  'Getter' function for member m_is_modfied
- void modify ()

  'Setter' function for member m_is_modified This setter only sets the modified-flag to true.
- int sequence_count () const

  'Getter' function for member m_sequence_count It is better to call this getter before bothering to even try to use a sequence.
- int sequence_max () const

  'Getter' function for member m_sequence_max
- bool is_control_status () const

  'Getter' function for member m_control_status
- void set_edit_sequence (int seqnum)

  'Setter' function for member m_edit_sequence
- void unset_edit_sequence (int seqnum)

  'Setter' function for member m_edit_sequence
- bool is_edit_sequence (int seqnum) const

  'Getter' function for member m_edit_sequence
- int get_beats_per_bar () const

  'Getter' function for member m_beats_per_bar
- void set_beats_per_bar (int bpm)

  'Setter' function for member m_beats_per_bar
- int get_beat_width () const

  'Getter' function for member m_beat_width
- void set_beat_width (int bw)

  'Setter' function for member m_beat_width
- const gui_assistant & gui () const

  'Getter' function for member m_gui_support The const getter.
- gui_assistant & gui ()

  'Getter' function for member m_gui_support The un-const getter.
- const keys_perform & keys () const

  'Getter' function for member m_gui_support.keys() The const getter.
- keys_perform & keys ()

  'Getter' function for member m_gui_support.keys() The un-const getter.
- mastermidibus & master_bus ()

  'Getter' function for member m_master_bus
- bool is_running () const

  'Getter' function for member m_running Could also be called "is_playing()".
- bool is_jack_running () const

  'Getter' function for member m_jack_asst.is_running() This function is useful for announcing the status of JACK in user-interface items that only have access to the perform object.
- bool is_paused () const

  'Getter' function for member m_is_paused
- bool is_pausable () const

  'Getter' function for member m_is_paused and ! m_jack_asst.is_running() We might just make this internal.
- void enregister (performcallback *pfcb)

Adds a pointer to an object to be notified by this perform object.

- void clear_all ()

  Clears all of the patterns/sequences.

- void launch (int ppqn)

  Calls the MIDI buss and JACK initialization functions and the input/output thread-launching functions.

- void new_sequence (int seq)

  Creates a new pattern/sequence for the given slot, and sets the new pattern's master MIDI bus address.

- void add_sequence (sequence *seq, int perf)

  Adds a pattern/sequence pointer to the list of patterns.

- void delete_sequence (int seq)

  Deletes a pattern/sequence by number.

- bool is_sequence_in_edit (int seq)

  Check if the pattern/sequence, given by number, has an edit in progress.

- void clear_sequence_triggers (int seq)

  Clears the patterns/sequence for the given sequence, if it is active.

- void print_triggers () const

  Shows all the triggers of all the sequences.

- void finish ()

  The rough opposite of launch(); it doesn't stop the threads.

- midipulse get_tick () const

  'Getter' function for member m_tick

- midipulse get_jack_tick () const

  'Getter' function for member m_jack_tick

- void set_jack_tick (midipulse tick)

  'Setter' function for member m_jack_tick

- void set_left_tick (midipulse tick, bool setstart=true)

  Set the left marker at the given tick.

- midipulse get_left_tick () const

  'Getter' function for member m_left_tick

- void set_start_tick (midipulse tick)

  'Setter' function for member m_starting_tick

- void set_right_tick (midipulse tick, bool setstart=true)

  Set the right marker at the given tick.

- midipulse get_right_tick () const

  'Getter' function for member m_right_tick

- void move_triggers (bool direction)

  If the left tick is less than the right tick, then, for each sequence that is active, its triggers are moved by the difference between the right and left in the specified direction.

- void copy_triggers ()

  If the left tick is less than the right tick, then, for each sequence that is active, its triggers are copied, offset by the difference between the right and left.

- void push_trigger_undo ()

  For every active sequence, call that sequence's push_trigger_undo() function.

- void pop_trigger_undo ()

  For every active sequence, call that sequence's pop_trigger_undo() function.

- void split_trigger (int seqnum, midipulse tick)

  Convenience function for perfroll's split-trigger functionality.

- midipulse get_max_trigger ()

  Locates the largest trigger value among the active sequences.

- void collapse ()

  Convenience function for perfedit's collapse functionality.

- void copy ()

  Convenience function for perfedit's copy functionality.
- void expand ()

  Convenience function for perfedit's expand functionality.
- midi_control & midi_control_toggle (int seq)

  Retrieves a reference to a value from m_midi_cc_toggle[].
- midi_control & midi_control_on (int seq)

  Retrieves a reference to a value from m_midi_cc_on[].
- midi_control & midi_control_off (int seq)

  Retrieves a reference to a value from m_midi_cc_off[].
- void handle_midi_control (int control, bool state)

  Handle the MIDI Control values that provide some automation for the application.
- const std::string & get_screen_set_notepad (int screen_set) const

  Retrieves the given string from m_screen_set_notepad[].
- const std::string & current_screen_set_notepad () const

  Returns the notepad text for the current screen-set.
- void set_screen_set_notepad (int screenset, const std::string &note)

  Copies the given string into m_screen_set_notepad[].
- void set_screen_set_notepad (const std::string &note)

  Sets the notepad text for the current screen-set.
- int get_screenset () const

  'Getter' function for member m_screenset
- void set_playing_screenset ()

  Sets the screen set that is active, based on the value of m_screenset.
- void set_screenset (int ss)

  Sets the m_screenset value (the index or ID of the current screen set).
- int get_playing_screenset () const

  'Getter' function for member m_playing_screen
- bool any_group_unmutes () const

  'Getter' function for member m_mute_group[] Returns true if there are any unmute statuses in the mute-group array.
- void mute_group_tracks ()

  If m_mode_group is true, then this function operates.
- void select_and_mute_group (int g_group)

  Select a mute group and then mutes the track in the group.
- void set_mode_group_mute ()

  'Setter' function for member m_mode_group
- void unset_mode_group_mute ()

  'Setter' function for member m_mode_group Unsets this member.
- void select_group_mute (int g_mute)

  If we're in group-learn mode, then this function gets the playing statuses of all of the sequences in the current play-screen, and copies them into the desired mute-group.
- void set_mode_group_learn ()

  Sets the group-mute mode, then the group-learn mode, then notifies all of the notification subscribers.
- void unset_mode_group_learn ()

  Notifies all of the notification subscribers that group-learn is being turned off.
- bool is_group_learning ()
- void set_and_copy_mute_group (int group)

  When in group-learn mode, for active sequences, the mute-group settings are set based on the playing status of each sequence.
- void start (bool state)

  If JACK is not running, call inner_start() with the given state.

- void stop ()

  If JACK is not running, call inner_stop().
- void start_jack ()

  If JACK is supported, starts the JACK transport.
- void stop_jack ()

  If JACK is supported, stops the JACK transport.
- void position_jack (bool state)

  If JACK is supported and running, sets the position of the transport.
- void off_sequences ()

  For all active patterns/sequences, set the playing state to false.
- void all_notes_off ()

  For all active patterns/sequences, turn off its playing notes.
- void set_active (int seq, bool active)

  Sets or unsets the active state of the given pattern/sequence number.
- void set_was_active (int seq)

  Sets was-active flags: main, edit, perf, and names.
- bool is_dirty_main (int seq)

  Checks the pattern/sequence for main-dirtiness.
- bool is_dirty_edit (int seq)

  Checks the pattern/sequence for edit-dirtiness.
- bool is_dirty_perf (int seq)

  Checks the pattern/sequence for perf-dirtiness.
- bool is_dirty_names (int seq)

  Checks the pattern/sequence for names-dirtiness.
- bool is_active (int seq) const

  Checks the pattern/sequence for activity.
- sequence * get_sequence (int seq)

  Retrieves the actual sequence, based on the pattern/sequence number.
- void reset_sequences (bool pause=false)

  For all active patterns/sequences, get its playing state, turn off the playing notes, set playing to false, zero the markers, and, if not in playback mode, restore the playing state.
- void play (midipulse tick)

  Plays all notes to the current tick.
- void set_orig_ticks (midipulse tick)

  For every pattern/sequence that is active, sets the "original tick" value for the pattern.
- void set_beats_per_minute (int bpm)

  Sets the value of the BPM into the master MIDI buss, after making sure it is squelched to be between 20 and 500.
- int get_beats_per_minute ()

  'Getter' function for member m_master_bus.get_beats_per_minute Retrieves the BPM setting of the master MIDI buss.
- void set_looping (bool looping)

  'Setter' function for member m_looping
- void set_sequence_control_status (int status)

  If the given status is present in the c_status_snapshot, the playing state is saved.
- void unset_sequence_control_status (int status)

  If the given status is present in the c_status_snapshot, the playing state is restored.
- void sequence_playing_toggle (int seq)

  If the given sequence is active, then it is toggled.
- void sequence_playing_change (int seq, bool on)

  Turn the playing of a sequence on or off, if it is active.
- void sequence_playing_on (int seq)

Calls sequence_playing_change() with a value of true.

- void sequence_playing_off (int seq)

  Calls sequence_playing_change() with a value of false.
- void mute_all_tracks (bool flag=true)

  Mutes/unmutes all tracks in the current set of active patterns/sequences.
- void toggle_all_tracks ()

  Toggles the mutes status of all tracks in the current set of active patterns/sequences.
- void mute_screenset (int ss, bool flag=true)

  Mutes/unmutes all tracks in the desired screen-set.
- void output_func ()

  Performance output function.
- void input_func ()

  This function is called by input_thread_func().
- void set_group_mute_state (int gtrack, bool muted)

  This function sets the mute state of an element in the m_mute_group array.
- bool get_group_mute_state (int gtrack)

  The opposite of set_group_mute_state(), it gets the value of the desired track.
- void set_offset (int offset)

  Calculates the offset into the screen sets.
- int get_offset () const

  'Getter' function for member m_offset
- void save_playing_state ()

  For all active patterns/sequences, this function gets the playing status and saves it in m_sequence_state[i].
- void restore_playing_state ()

  For all active patterns/sequences, this function gets the playing status from m_sequence_state[i] and sets it for the sequence.
- std::string key_name (unsigned int k) const

  Here follows a few forwarding functions for the keys_perform-derived classes.
- keys_perform::SlotMap & get_key_events ()

  Forwarding function for key events.
- keys_perform::SlotMap & get_key_groups ()

  Forwarding function for key groups.
- keys_perform::RevSlotMap & get_key_events_rev ()

  Forwarding function for reverse key events.
- keys_perform::RevSlotMap & get_key_groups_rev ()

  Forwarding function for reverse key groups.
- bool show_ui_sequence_key () const

  'Getter' function for member m_show_ui_sequency_key Provides access to keys().show_ui_sequence_key().
- void show_ui_sequence_key (bool flag)

  'Setter' function for member m_show_ui_sequency_key
- bool show_ui_sequence_number () const

  'Getter' function for member m_show_ui_sequency_number Provides access to keys().show_ui_sequence_number().
- void show_ui_sequence_number (bool flag)

  'Getter' function for member m_show_ui_sequency_number
- unsigned int lookup_keyevent_key (int seqnum)

  Gets the event key for the given sequence.
- long lookup_keyevent_seq (unsigned int keycode)

  Gets the sequence number for the given event key.
- unsigned int lookup_keygroup_key (long groupnum)

  Gets the group key for the given sequence.
- long lookup_keygroup_group (unsigned int keycode)

Gets the group number for the given group key.

- void start_playing (bool songmode=false)

  Encapsulates a series of calls used in mainwnd.
- void pause_playing ()

  Pause playback, so that progress bars stay where they are, and playback always resumes where it left off, even in ALSA mode.
- void stop_playing ()

  Encapsulates a series of calls used in mainwnd.
- void start_key (bool songmode=false)

  Invoke the start key functionality.
- void pause_key (bool songmode=false)

  Invoke the pause key functionality.
- void stop_key ()

  Invoke the stop key functionality.
- void learn_toggle ()

  Encapsulates some calls used in mainwnd.
- int decrement_beats_per_minute ()

  Encapsulates some calls used in mainwnd.
- int increment_beats_per_minute ()

  Encapsulates some calls used in mainwnd.
- int decrement_screenset ()

  Encapsulates some calls used in mainwnd.
- int increment_screenset ()

  Encapsulates some calls used in mainwnd.
- bool highlight (const sequence &seq) const

  True if a sequence is empty and should be highlighted.
- bool is_smf_0 (const sequence &seq) const

  True if the sequence is an SMF 0 sequence.
- void sequence_key (int seq)

  Handle a sequence key to toggle the playing of an active pattern in the selected screen-set.
- std::string sequence_label (const sequence &seq)

  Provides a way to format the sequence parameters string for display in the mainwid or perfnames modules.
- void set_input_bus (int bus, bool input_active)

  Sets the input bus, and handles the special "key labels on sequence" and "sequence numbers on sequence" functionality.
- bool mainwnd_key_event (const keystroke &k)

  Provided for mainwnd :: on_key_press_event() and mainwnd :: on_key_release_event() to call.
- bool perfroll_key_event (const keystroke &k, int drop_sequence)

  Provided for perfroll :: on_key_press_event() and perfroll :: on_key_release_event() to call.
- bool playback_key_event (const keystroke &k, bool songmode=false)

  New function provided to unify the stop/start (space/escape) behavior of the various windows where playback can be started, paused, or stopped.

Private Member Functions

- int max_active_set () const

  Checks the whole universe of sequences to determine the current last-active set, that is, the highest set that has any active sequences in it.
- void launch_input_thread ()

  Creates the input thread using input_thread_func().
- void launch_output_thread ()

Creates the output thread using output_thread_func().

- bool init_jack ()

  Initializes JACK support, if SEQ64_JACK_SUPPORT is defined.
- bool deinit_jack ()

  Tears down the JACK infrastructure.
- bool seq_in_playing_screen (int seq)

  A helper function for determining if the mode group is in force, the playing screenset is the same as the current screenset, and the sequence is in the range of the playing screenset.
- void is_modified (bool flag)

  'Setter' function for member m_is_modified
- bool is_midi_control_valid (int seq) const

  Checks the parameter against c_midi_controls.
- bool is_screenset_valid (int screenset) const

  Checks the screenset against m_max_sets.
- void set_running (bool running)

  'Setter' function for member m_running
- void set_playback_mode (bool playbackmode)

  'Setter' function for member m_playback_mode
- int mute_group_offset (int track)

  A helper function to calculate the index into the mute-group array, based on the desired track.
- bool is_seq_valid (int seq) const

  Provides common code to check for the bounds of a sequence number.
- bool is_mseq_valid (int seq) const

  Validates the sequence number, which is important since they're currently used as array indices.
- bool install_sequence (sequence *seq, int seqnum)

  A private helper function for add_sequence() and new_sequence().
- void inner_start (bool state)

  Locks on m_condition_var.
- void inner_stop ()

  Unconditionally, and without locking, clears the running status, resets the sequences, and sets m_usemidiclock false.
- int clamp_track (int track) const

  Provides common code to keep the track value valid.
- void set_all_key_events ()

  Pass-along function for keys().set_all_key_events.
- void set_all_key_groups ()

  Pass-along function for keys().set_all_key_events.
- void set_key_event (unsigned int keycode, long sequence_slot)

  At construction time, this function sets up one keycode and one event slot.
- void set_key_group (unsigned int keycode, long group_slot)

  At construction time, this function sets up one keycode and one group slot.

Private Attributes

- gui_assistant & m_gui_support

  Support for a wide range of GUI-related operations.
- bool m_mute_group [c_gmute_tracks]

  Mute group support.
- bool m_tracks_mute_state [c_seqs_in_set]

  Holds the current mute states of each track.
- bool m_mode_group

If true, indicates that a mode group is selected, and playing statuses will be "memorized".

- bool m_mode_group_learn

  If true, indicates that a group learn is selected, which also "memorizes" a mode group, and notifies subscribers of a group-learn change.
- int m_mute_group_selected

  Selects a group to mute.
- int m_playing_screen

  Playing screen support.
- int m_playscreen_offset

  Playing screen sequence number offset.
- sequence * m_seqs [c_max_sequence]

  Provides a "vector" of patterns/sequences.
- bool m_seqs_active [c_max_sequence]

  Each boolean value in this array is set to true if a sequence is active, meaning that it will be used to hold some kind of MIDI data, even if only Meta events.
- bool m_was_active_main [c_max_sequence]

  Each boolean value in this array is set to true if a sequence was active, meaning that it was found to be active at the time we were setting it to inactive.
- bool m_was_active_edit [c_max_sequence]

  Each boolean value in this array is set to true if a sequence was active, meaning that it was found to be active at the time we were setting it to inactive.
- bool m_was_active_perf [c_max_sequence]

  Each boolean value in this array is set to true if a sequence was active, meaning that it was found to be active at the time we were setting it to inactive.
- bool m_was_active_names [c_max_sequence]

  Each boolean value in this array is set to true if a sequence was active, meaning that it was found to be active at the time we were setting it to inactive.
- bool m_sequence_state [c_max_sequence]

  Saves the current playing state of each pattern.
- mastermidibus m_master_bus

  Provides our MIDI buss.
- pthread_t m_out_thread

  Provides information for managing pthreads.
- pthread_t m_in_thread

  Provides a "handle" to the input thread.
- bool m_out_thread_launched

  Indicates that the output thread has been started.
- bool m_in_thread_launched

  Indicates that the input thread has been started.
- bool m_running
- bool m_inputing

  Indicates that events are being written to the MIDI input busses in the input thread.
- bool m_outputing

  Indicates that events are being written to the MIDI output busses in the output thread.
- bool m_looping

  Indicates that status of the "loop" button in the performance editor.
- bool m_playback_mode

  Specifies the playback mode.
- int m_ppqn

  Holds the current PPQN for usage in various actions.
- int m_beats_per_bar

  Holds the beats/bar value as obtained from the MIDI file.

- int m_beat_width

  Holds the beat width value as obtained from the MIDI file.
- midipulse m_one_measure

  Holds the "one measure's worth" of pulses (ticks), which is normally m_ppqn ∗ 4.
- midipulse m_left_tick

  Holds the position of the left (L) marker, and it is first defined as 0.
- midipulse m_right_tick

  Holds the position of the right (R) marker, and it is first defined as the end of the fourth measure.
- midipulse m_starting_tick

  Holds the starting tick for playing.
- midipulse m_tick

  MIDI Clock support.
- midipulse m_jack_tick

  Let's try to save the last JACK pad structure tick for re-use with resume after pausing.
- bool m_usemidiclock

  More MIDI clock support.
- bool m_midiclockrunning

  More MIDI clock support.
- int m_midiclocktick

  More MIDI clock support.
- int m_midiclockpos

  More MIDI clock support.
- bool m_is_paused

  Support for pause, which does not reset the "last tick" when playback stops/starts.
- std::string m_screen_set_notepad [c_max_sets]

  Used in the mainwnd class to set the notepad text for the given set.
- midi_control m_midi_cc_toggle [c_midi_controls]

  Provides the settings of MIDI Toggle, as read from the "rc" file.
- midi_control m_midi_cc_on [c_midi_controls]

  Provides the settings of MIDI On, as read from the "rc" file.
- midi_control m_midi_cc_off [c_midi_controls]

  Provides the settings of MIDI Off, as read from the "rc" file.
- int m_offset

  Holds the current offset into the screen-sets.
- int m_control_status

  Holds the OR'ed control status values.
- int m_screenset

  Indicates the number of the currently-selected screen-set.
- int m_seqs_in_set

  We will eventually replace c_seqs_in_set with this member, which defaults to the value of c_seqs_in_set.
- int m_max_sets

  A replacement for the c_max_sets constant.
- int m_sequence_count

  Keeps track of created sequences, whether or not they are active.
- int m_sequence_max

  A replacement for the c_max_sequence constant.
- int m_edit_sequence

  Hold the number of the currently-in-edit sequence.
- bool m_is_modified

  It may be a good idea to eventually centralize all of the dirtiness of a performance here.
- condition_var m_condition_var

A condition variable to protect playback.

- jack_assistant m_jack_asst

  A wrapper object for the JACK support of this application.

- std::vector< performcallback * > m_notify

Static Private Attributes

- static midi_control sm_mc_dummy

  Provides a dummy, inactive midi_control object to handle out-of-range midi_control indicies.

Friends

- class jack_assistant
- class keybindentry
- class midifile
- class optionsfile
- class options
- int jack_sync_callback (jack_transport_state_t state, jack_position_t *pos, void *arg)

  Global functions for JACK support and JACK sessions.

12.50.1 Detailed Description

It has way too many data members, one of them public. Might be ripe for refactoring. That has its own dangers, of course.

12.50.2 Constructor & Destructor Documentation

12.50.2.1 seq64::perform::perform (gui_assistant & *mygui*, int *ppqn* = SEQ64_USE_DEFAULT_PPQN)

Also note that we have a little issue with the fact that various sequences (patterns) can potentially have different beats/measure and beat-width values.

Currently, when reading the MIDI file, the beats/minute value is obtained from the MIDI file, if present, and this value is passed to perform::set_beats_per_minute(), which forwards it to the master MIDI buss and JACK assistant objects. This Tempo setting comes from both the Tempo meta event in track 0, and from the Seq24's c_bpm SeqSpec section! This setting is now also made for the two Time Signature values.

Parameters

mygui	Provides access to the GUI assistant that holds many things, including the containers of keys and the "events" they provide. This is a base-class reference; for a real class, see the gui_assistant_gtk2 class in the seq_gtkmm2 GUI-specific library. Note that we access the m_gui_support member using the gui() accessor function.
ppqn	The default, choosable, or actual PPQN value.

12.50.2.2 seq64::perform::~perform ( )

Finally, any active or inactive (but allocated) patterns/sequences are deleted, and their pointers nullified.

12.50.3 Member Function Documentation

12.50.3.1 bool seq64::perform::is_modified ( ) const [inline]

12.50.3.2 void seq64::perform::modify ( ) [inline]

The setter that will, is_modified(), is private. No one but perfrom and its friends should falsify this flag.

12.50.3.3 int seq64::perform::sequence_count ( ) const [inline]

In many cases at startup, or when loading a file, there are no sequences yet, and still the code calls functions that try to access them.

12.50.3.4 int seq64::perform::sequence_max ( ) const [inline]

12.50.3.5 bool seq64::perform::is_control_status ( ) const [inline]

Returns

Returns true if the m_control_status value is non-zero, which means that there is a queue, replace, or snapshot functionality in progress.

12.50.3.6 void seq64::perform::set_edit_sequence (int *seqnum*) [inline]

Parameters

seqnum	Pass in -1 to disable the edit-sequence number unconditionally. Use unset_edit_sequence() to disable it if it matches the current edit-sequence number.

12.50.3.7 void seq64::perform::unset_edit_sequence (int *seqnum*) [inline]

Disables the edit-sequence number if it matches the parameter.

Parameters

seqnum	The sequence number of the sequence to unset.

12.50.3.8 bool seq64::perform::is_edit_sequence (int *seqnum*) const [inline]

Parameters

seqnum	Tests the parameter against m_edit_sequence. Returns true if that member is not -1, and the parameter matches it.

12.50.3.9 int seq64::perform::get_beats_per_bar ( ) const [inline]

12.50.3.10 void seq64::perform::set_beats_per_bar (int *bpm*) [inline]

Parameters

bpm	Provides the value for beats/measure. Also used to set the beats/measure in the JACK assistant object.

12.50.3.11 int seq64::perform::get_beat_width ( ) const [inline]

12.50.3.12 void seq64::perform::set_beat_width (int *bw*) [inline]

Parameters

bw	Provides the value for beat-width. Also used to set the beat-width in the JACK assistant object.

12.50.3.13 const gui_assistant& seq64::perform::gui ( ) const [inline]

12.50.3.14 gui_assistant& seq64::perform::gui ( ) [inline]

12.50.3.15 const keys_perform& seq64::perform::keys ( ) const [inline]

12.50.3.16 keys_perform& seq64::perform::keys ( ) [inline]

12.50.3.17 mastermidibus& seq64::perform::master_bus ( ) [inline]

12.50.3.18 bool seq64::perform::is_running ( ) const [inline]

12.50.3.19 bool seq64::perform::is_jack_running ( ) const [inline]

12.50.3.20 bool seq64::perform::is_paused ( ) const [inline]

12.50.3.21 bool seq64::perform::is_pausable ( ) const [inline]

12.50.3.22 void seq64::perform::enregister (performcallback * *pfcb*) [inline]

Parameters

pfcb	Provides the pointer to the performance callback.

12.50.3.23 void seq64::perform::clear_all ( )

The mainwnd module calls this function. Note that perform now handles the "is modified" flag on behalf of all external objects, to centralize and simplify the dirtying of a MIDI tune.

Anything else to clear? What about all the other sequence flags? We can beef up delete_sequence() for them, at some point.

12.50.3.24 void seq64::perform::launch (int *ppqn*)

This function is called in main(). We collected all the calls here as a simplification, and renamed it because it is more than just initialization. This function must be called after the perform constructor and after the configuration file and command-line configuration overrides.

Parameters

ppqn	Provides the PPQN value, which is either the default value (192) or is read from the "user" configuration file.

12.50.3.25 void seq64::perform::new_sequence (int *seq*)

Then it activates the pattern [this is done in the install_sequence() function]. It doesn't deal with thrown exceptions.

This function is called by the seqmenu and mainwid objects to create a new sequence. We now pass this sequence to install_sequence() to better handle potential memory leakage, and to make sure the sequence gets counted. Also, adding a new sequence from the user-interface is a significant modification, so the "is modified" flag gets set.

Change Note ca 2016-05-15 If enabled, wire in the MIDI buss override.

Parameters

seq	The prospective sequence number of the new sequence.

12.50.3.26 void seq64::perform::add_sequence (sequence * *seq,* int *prefnum*)

No check is made for a null pointer, but the install_sequence() call will make sure such a pointer is officially logged.

This function checks for the preferred sequence number. This is the number that was specified by the Sequence Number meta-event for the current track. If the preferred sequence number is in the valid range (0 to m_sequence↩ _max) and it is not active, add it and activate it. Otherwise, iterate through all patterns from prefnum to m_↩ sequence_max and add and activate the first one that is not active, and then finish.

Finally, note that this function is used only by midifile, when reading in a MIDI song. Therefore, the "is modified" flag is *not* set by this function; loading a sequence from a file is not a modification that should lead to a prompt for saving the file later.

Todo Shouldn't we wrap around the sequence list if we can't find an empty sequence slot after prefnum?

Warning

The logic of the if-statement in this function was such that *prefnum* could be out-of-bounds in the else-clause. We reworked the logic to be airtight. This bug was caught by gcc 4.8.3 on CentOS, but not on gcc 4.9.3 on Debian Sid!

Parameters

seq	The pointer to the pattern/sequence to add.
prefnum	The preferred sequence number of the pattern, as explained above. If this value is out-of-range, then it is basically ignored.

12.50.3.27 void seq64::perform::delete_sequence (int *seq*)

We now also solidify the deletion by setting the pointer to null after deletion, so it will blow up if accidentally accessed. The final act is to raise the "is modified" flag, since deleting an existing sequence is always a significant modification.

Now, this function obviously sets the "active" flag for the sequence to false. But there are a few other flags that are not modified; shouldn't we also falsify them here?

Parameters

seq	The sequence number of the sequence to be deleted. It is validated.

12.50.3.28 bool seq64::perform::is_sequence_in_edit (int *seq*)

Parameters

seq	Provides the sequence number to be checked.

Returns

Returns truen if the sequence's get_editing() call returns true. Otherwise, false is returned, which can also indicate an illegal sequence number.

12.50.3.29 void seq64::perform::clear_sequence_triggers (int *seq*)

Parameters

seq	Provides the desired sequence. The is_active() function validates this value.

12.50.3.30 void seq64::perform::print_triggers ( ) const

12.50.3.31 void seq64::perform::finish ( ) [inline]

A minor simplification for the main() routine, hides the JACK support macro.

12.50.3.32 midipulse seq64::perform::get_tick ( ) const [inline]

12.50.3.33 midipulse seq64::perform::get_jack_tick ( ) const [inline]

12.50.3.34 void seq64::perform::set_jack_tick (midipulse *tick*) [inline]

Parameters

tick	Provides the current JACK tick (pulse) value to set.

12.50.3.35 void seq64::perform::set_left_tick (midipulse *tick,* bool *setstart* = true)

We let the caller determine if this setting is a modification. If the left tick is later than the right tick, the right tick is move to one measure past the left tick.

Todo The perform::m_one_measure member is currently hardwired to PPQN ∗ 4.

Parameters

tick	The tick (MIDI pulse) at which to place the left tick. If the left tick is greater than or equal to the right tick, then the right ticked is moved forward by one "measure's length" (m_ppqn ∗ 4) past the left tick.
setstart	If true (the default, and long-standing implicit setting), then the starting tick is also set to the left tick.

12.50.3.36 midipulse seq64::perform::get_left_tick ( ) const [inline]

12.50.3.37 void seq64::perform::set_start_tick (midipulse *tick*) [inline]

Parameters

tick	Provides the starting JACK tick (pulse) value to set.

12.50.3.38 void seq64::perform::set_right_tick (midipulse *tick,* bool *setstart* = true)

This setting is made only if the tick parameter is at or beyond the first measure. We let the caller determine is this setting is a modification.

Parameters

tick	The tick (MIDI pulse) at which to place the right tick. If less than or equal to the left tick setting, then the left tick is backed up by one "measure's worth" (m_ppqn ∗ 4) worth of ticks from the new right tick.
setstart	If true (the default, and long-standing implicit setting), then the starting tick is also set to the left tick, if that got changed.

12.50.3.39 midipulse seq64::perform::get_right_tick ( ) const [inline]

12.50.3.40 void seq64::perform::move_triggers (bool *direction*)

Parameters

direction	Specifies the desired direction; false = left, true = right.

12.50.3.41 void seq64::perform::copy_triggers ( )

This copies the triggers between the L marker and R marker to the R marker.

12.50.3.42 void seq64::perform::push_trigger_undo ( )

Too bad we cannot yet keep track of all the undoes for the sake of properly handling the "is modified" flag.

12.50.3.43 void seq64::perform::pop_trigger_undo ( )

12.50.3.44 void seq64::perform::split_trigger (int *seqnum*, midipulse *tick*)

Parameters

seqnum	Indicates the sequence that needs to have its trigger split.
tick	The MIDI pulse number at which the trigger should be split.

12.50.3.45 midipulse seq64::perform::get_max_trigger ( )

Returns

Returns the highest trigger value, or zero. It is not clear why this function doesn't return a "no trigger found" value. Is there always at least one trigger, at 0?

12.50.3.46 void seq64::perform::collapse ( ) [inline]

12.50.3.47 void seq64::perform::copy ( ) [inline]

12.50.3.48 void seq64::perform::expand ( ) [inline]

12.50.3.49 midi_control & seq64::perform::midi_control_toggle (int *seq*)

Parameters

seq	Provides the index to pass to is_midi_control_valid() to obtain a control value (such as c_midi_control_bpm_up) to use to retrieve the desired midi_control object. Note that this value is unsigned simply to make the legality check of the parameter easier.

Returns

Returns the "toggle" value if the sequence is valid, and a reference to sm_mc_dummy otherwise.

12.50.3.50 midi_control & seq64::perform::midi_control_on (int *seq*)

Parameters

seq	Provides the index to pass to is_midi_control_valid() to obtain a control value (such as c_midi_control_bpm_up) to use to retrieve the desired midi_control object.

Returns

Returns the "on" value if the sequence is valid, and a reference to sm_mc_dummy otherwise.

12.50.3.51 midi_control & seq64::perform::midi_control_off (int *seq*)

Parameters

seq	Provides a control value (such as c_midi_control_bpm_up) to use to retrieve the desired midi_control object.

Returns

Returns the "off" value if the sequence is valid, and a reference to sm_mc_dummy otherwise.

12.50.3.52 void seq64::perform::handle_midi_control (int *ctrl*, bool *state*)

Parameters

ctrl	The MIDI control value to use to perform an operation.
state	The state of the control, used with the following values:

```
c_midi_control_mod_replace
c_midi_control_mod_snapshot
c_midi_control_mod_queue
c_midi_control_mod_gmute
c_midi_control_mod_glearn
```

12.50.3.53 const std::string & seq64::perform::get_screen_set_notepad (int *screenset*) const

Parameters

screenset	The ID number of the string set, an index into the m_screen_set_notepad[] array. This value is validated.

Returns

Returns a reference to the desired string, or to an empty string if the screen-set number is invalid.

12.50.3.54 const std::string& seq64::perform::current_screen_set_notepad ( ) const [inline]

12.50.3.55 void seq64::perform::set_screen_set_notepad (int *screenset,* const std::string & *notepad*)

Parameters

screenset	The ID number of the string set, an index into the m_screen_set_xxx[] arrays.
notepad	Provides the string date to copy into the notepad. Not sure why a pointer is used, instead of nice "const std::string &" parameter. And this pointer isn't checked. Fixed.

12.50.3.56 void seq64::perform::set_screen_set_notepad (const std::string & *note*) [inline]

Parameters

note	The string value to set into the notepad text.

12.50.3.57 int seq64::perform::get_screenset ( ) const [inline]

12.50.3.58 void seq64::perform::set_playing_screenset ( )

This function is called when one of the snapshot keys is pressed.

For each value up to m_seqs_in_set (32), the index of the current sequence in the current screen set (m_playing↩_screen) is obtained. If the sequence is active and the sequence actually exists, it is processed; null sequences are no longer flagged as an error, they are just ignored.

Modifies m_playing_screen, m_playscreen_offset, stores the current playing-status of each sequence in m_tracks↩_mute_state[], and then calls mute_group_tracks(), turns on unmuted tracks in the current screen-set.

Basically, this function retrieves and saves the playing status of the sequences in the current play-screen, sets the play-screen to the current screen-set, and then mutes the previous play-screen. It is called via the c_midi_control↩_play_ss value or via the set-playing-screen-set keystroke.

12.50.3.59 void seq64::perform::set_screenset (int *ss*)

It's not clear that we need to set the "is modified" flag just because we changed the screen set, so we don't.

As a new feature, we would like to queue-mute the previous screenset, and queue-unmute the newly-selected screenset. Still working on getting it right.

Parameters

ss	The index of the desired new screen set. It is forced to range from 0 to m_max_sets - 1. The clamping seems weird, but hews to seq24. What it does is let the user wrap around the screen-sets in the user interface.

12.50.3.60 int seq64::perform::get_playing_screenset ( ) const [inline]

12.50.3.61 bool seq64::perform::any_group_unmutes ( ) const

If they're all zero, we don't need to save them.

12.50.3.62 void seq64::perform::mute_group_tracks ( )

It loops through every screen-set. In each screen-set, it acts on each active sequence. If the active sequence is in the current "in-view" screen-set (m_screenset as opposed to m_playing_screen), and its m_track_mute_state[] is true, then the sequence is turned on, otherwise it is turned off.

Change Note tdeagan 2015-12-22 via git pull. Replaced m_playing_screen with m_screenset.

Change Note 2016-05-06 It seems to us that the for (i) clause should have i range from 0 to m_max_sets, not m_seqs_in_set. So let's do it, pre-emptively.

12.50.3.63 void seq64::perform::select_and_mute_group (int *group*)

Called in perform and in mainwnd.

Parameters

group	Provides the group number for the group to be muted.

12.50.3.64 void seq64::perform::set_mode_group_mute ( ) [inline]

12.50.3.65 void seq64::perform::unset_mode_group_mute ( ) [inline]

12.50.3.66 void seq64::perform::select_group_mute (int *mutegroup*)

Then, no matter what, it makes the desired mute-group the selected mute-group. Compare to set_and_copy_↩ mute_group().

One thing to note is that, once saved, then, if used, it is applied to the current screen-set, even if it is not the screen-set whose playing status were saved.

Parameters

mutegroup	The number of the desired mute group, clamped to be between 0 and m_seqs_in_set-1. Obviously, it is the set whose state is to be stored, if in group-learn mode.

12.50.3.67 void seq64::perform::set_mode_group_learn ( )

This function is called via a MIDI control c_midi_control_mod_glearn and via the group-learn keystroke.

12.50.3.68 void seq64::perform::unset_mode_group_learn ( )

Then unsets the group-learn mode flag. This function is called via a MIDI control c_midi_control_mod_glearn, via the group-learn keystroke, and in mainwnd::on_key_press_event(), to end the group-learn mode.

Shouldn't this function also call this one, to perfectly complement set_mode_group_learn: unset_mode_group_↩ mute(). Too tricky.

12.50.3.69 bool seq64::perform::is_group_learning ( ) [inline]

12.50.3.70 void seq64::perform::set_and_copy_mute_group (int *mutegroup*)

Then the mute-group is stored in m_tracks_mute_state[], which holds states for only the number of sequences in a set.

Compare to select_group_mute(); its main difference is that it will at least copy the states even if not in group-learn mode. And, if in group-learn mode, it will grab the playing states of the sequences before copying them.

This function is used only once, in select_and_mute_group(). It used to be called just select_mute_group(), but that's too easy to confuse with select_group_mute().

Change Note tdeagan 2015-12-22 via git pull: git pull https://github.com/TDeagan/sequencer64.↩ git mute_groups m_screenset replaces m_playscreen_offset.

Parameters

mutegroup	Provides the mute-group to select.

12.50.3.71 void seq64::perform::start (bool *state*)

Parameters

state	What does this state mean?

12.50.3.72 void seq64::perform::stop ( )

The logic seems backward here, in that we call inner_stop() if JACK is not running. Or perhaps we misunderstand the meaning of m_jack_running?

12.50.3.73 void seq64::perform::start_jack ( ) [inline]

12.50.3.74 void seq64::perform::stop_jack ( ) [inline]

12.50.3.75 void seq64::perform::position_jack (bool *state*)

12.50.3.76 void seq64::perform::off_sequences ( )

12.50.3.77 void seq64::perform::all_notes_off ( )

Then flush the master MIDI buss.

12.50.3.78 void seq64::perform::set_active (int *seq*, bool *active*)

If setting it active, the sequence::number() setter is called. It won't modify the sequence's internal copy of the sequence number if it has already been set.

Parameters

seq	Provides the prospective sequence number.
active	True if the sequence is to be set to the active state.

12.50.3.79 void seq64::perform::set_was_active (int *seq*)

Why do we need this routine?

Parameters

seq	The pattern number. It is checked for validity.

12.50.3.80 bool seq64::perform::is_dirty_main (int *seq*)

See the sequence::is_dirty_main() function.

Parameters

seq	The pattern number. It is checked for validity.

Returns

Returns the was-active-main flag value, before setting it to false. Returns false if the pattern was invalid.

12.50.3.81 bool seq64::perform::is_dirty_edit (int *seq*)

Parameters

seq	The pattern number. It is checked for validity.

Returns

Returns the was-active-edit flag value, before setting it to false. Returns false if the pattern was invalid.

12.50.3.82 bool seq64::perform::is_dirty_perf (int *seq*)

Parameters

seq	The pattern number. It is checked for validity.

Returns

Returns the was-active-perf flag value, before setting it to false. Returns false if the pattern/sequence number was invalid.

12.50.3.83 bool seq64::perform::is_dirty_names (int *seq*)

Parameters

seq	The pattern number. It is checked for validity.

Returns

Returns the was-active-names flag value, before setting it to false. Returns false if the pattern/sequence number was invalid.

12.50.3.84 bool seq64::perform::is_active (int *seq*) const [inline]

Todo We should have the sequence object keep track of its own activity and access that via a reference or pointer.

Parameters

seq	The pattern number. It is checked for invalidity. This can lead to "too many" (i.e. redundant) checks, but we're trying to centralize such checks in this function.

Returns

Returns the value of the active-flag, or false if the sequence was invalid or null.

12.50.3.85 sequence* seq64::perform::get_sequence (int *seq*) [inline]

Parameters

seq	The prospective sequence number.

Returns

Returns the value of m_seqs[seq] if seq is valid. Otherwise, a null pointer is returned.

12.50.3.86 void seq64::perform::reset_sequences (bool *pause* = `false`)

Note that these calls are folded into one member function of the sequence class. Finally, flush the master MIDI buss.

12.50.3.87 void seq64::perform::play (midipulse *tick*)

Starts the playing of all the patterns/sequences.

This function just runs down the list of sequences and has them dump their events. It skips sequences that have no playable MIDI events.

Parameters

tick	Provides the tick at which to start playing.

12.50.3.88 void seq64::perform::set_orig_ticks (midipulse *tick*)

This is really the "last tick" value, so we renamed sequence::set_orig_tick() to sequence::set_last_tick().

Parameters

tick	Provides the last-tick value to be set for each sequence that is active.

12.50.3.89 void seq64::perform::set_beats_per_minute (int *bpm*)

Replaces perform::set_bpm() from seq24.

The value is set only if neither JACK nor this performance object are running.

It's not clear that we need to set the "is modified" flag just because we changed the beats per minute. This setting does get saved to the MIDI file, with the c_bpmtag.

Parameters

bpm	Provides the beats/minute value to be set. It is clamped, if necessary, between the values SEQ64_MINIMUM_BPM to SEQ64_MAXIMUM_BPM. They provide a wide range of speeds, well beyond what normal music needs.

12.50.3.90 int seq64::perform::get_beats_per_minute ( ) `[inline]`

Returns

Returns the value of beats/minute from the master buss.

12.50.3.91 void seq64::perform::set_looping (bool *looping*) [inline]

Parameters

looping	The boolean value to set for looping, used in the performance editor.

12.50.3.92 void seq64::perform::set_sequence_control_status (int *status*)

Then the given status is OR'd into the m_control_status.

Parameters

status	The status to be used.

12.50.3.93 void seq64::perform::unset_sequence_control_status (int *status*)

Then the given status is reversed in m_control_status.

Parameters

status	The status to be used.

12.50.3.94 void seq64::perform::sequence_playing_toggle (int *seq*)

If the m_control_status is c_status_queue, then the sequence's toggle_queued() function is called. Otherwise, if it is c_status_replace, then the status is unset, and all sequences (?) are turned off. Then the sequence's toggle-playing() function is called.

Parameters

seq	The sequence number of the sequence to be potentially toggled.

12.50.3.95 void seq64::perform::sequence_playing_change (int *seq*, bool *on*)

Used for the implementation of sequence_playing_on() and sequence_playing_off().

Parameters

seq	The number of the sequence to be turned off.
on	True if the sequence is to be turned on, false if it is to be turned off.

12.50.3.96 void seq64::perform::sequence_playing_on (int *seq*) [inline]

Parameters

seq	The sequence number of the sequence to turn on.

12.50.3.97 void seq64::perform::sequence_playing_off (int *seq*) [inline]

Parameters

seq	The sequence number of the sequence to turn off.

12.50.3.98 void seq64::perform::mute_all_tracks (bool *flag* = true)

Covers tracks from 0 to m_sequence_max.

We have to also set the sequence's playing status, in opposition to the mute status, in order to see the sequence status change on the user-interface. HMMMMMM.

Parameters

flag	If true (the default), the song-mute of the sequence is turned on. Otherwise, it is turned off.

12.50.3.99 void seq64::perform::toggle_all_tracks ( )

Covers tracks from 0 to m_sequence_max.

Parameters

flag	If true (the default), the song-mute of the sequence is turned on. Otherwise, it is turned off.

12.50.3.100 void seq64::perform::mute_screenset (int *ss*, bool *flag* = true)

Parameters

flag	If true (the default), the song-mute of the sequence is turned on. Otherwise, it is turned off.

12.50.3.101 void seq64::perform::output_func ( )

This function is called by the free function output_thread_func(). Here's how it works:

```
-   It runs while m_outputing is true.
-   MORE TO COME.  Yeah, a lot more to come.  It is a complex
    function.
```

Change Note ca 2016-01-26 Hurray, seq24 is coming back to life! We see that there is a fix for clock tick drift here, which relies on using long and long long values. See the Changelog for seq24 0.9.3.

1. Get delta time (current - last).
2. Get delta ticks from time.
3. Add to current_ticks.
4. Compute prebuffer ticks.
5. Play from current tick to prebuffer.

Figure out how much time we need to sleep, and do it.

Now we want to trigger every c_thread_trigger_width_us, and it took us delta_us to play(). Also known as the "sleeping_us".

Check MIDI clock adjustment. Note that we replaced "60000000.0f / m_ppqn / bpm" with a call to a function. We also removed the "f" specification from the constants.

12.50.3.102 void seq64::perform::input_func ( )

12.50.3.103 void seq64::perform::set_group_mute_state (int *gtrack*, bool *muted*) [inline]

The index value is the track number offset by the number of the selected mute group (which is equivalent to a set number) times the number of sequences in a set. This function is used in midifile and optionsfile when parsing the file to get the initial mute-groups.

Parameters

gtrack	The number of the track to be muted/unmuted.
muted	This boolean indicates the state to which the track should be set.

12.50.3.104 bool seq64::perform::get_group_mute_state (int *gtrack*) [inline]

Uses the mute_group_offset() function. This function is used in midifile and optionsfile when writing the file to get the initial mute-groups.

Parameters

gtrack	The number of the track for which the state is to be obtained. Like set_group_mute_state(), this value is offset by adding m_mute_group_selected $*$ m_seqs_in_set.

Returns

Returns the desired m_mute_group[] value.

12.50.3.105 void seq64::perform::set_offset (int *offset*) [inline]

Sets `m_offset = offset * c_mainwnd_rows * c_mainwnd_cols`.

Parameters

offset	The desired offset.

12.50.3.106 int seq64::perform::get_offset ( ) const [inline]

12.50.3.107 void seq64::perform::save_playing_state ( )

Inactive patterns get the value set to false. Used in unsetting the snapshot status (c_status_snapshot).

12.50.3.108 void seq64::perform::restore_playing_state ( )

Used in unsetting the snapshot status (c_status_snapshot).

12.50.3.109 std::string seq64::perform::key_name (unsigned int *k*) const [inline]

Parameters

k	The key number for which to return the string name of the key.

12.50.3.110 keys_perform::SlotMap& seq64::perform::get_key_events ( ) [inline]

12.50.3.111 keys_perform::SlotMap& seq64::perform::get_key_groups ( ) [inline]

12.50.3.112 keys_perform::RevSlotMap& seq64::perform::get_key_events_rev ( ) [inline]

12.50.3.113 keys_perform::RevSlotMap& seq64::perform::get_key_groups_rev ( ) [inline]

12.50.3.114 bool seq64::perform::show_ui_sequence_key ( ) const [inline]

Used in mainwid, options, optionsfile, userfile, and perform.

12.50.3.115 void seq64::perform::show_ui_sequence_key (bool *flag*) [inline]

Parameters

flag	Provides the flag to set into keys().show_ui_sequence_key().

12.50.3.116 bool seq64::perform::show_ui_sequence_number ( ) const [inline]

Used in mainwid, optionsfile, and perform.

12.50.3.117 void seq64::perform::show_ui_sequence_number (bool *flag*) [inline]

Parameters

flag	Provides the value to set into keys().show_ui_sequence_number().

12.50.3.118 unsigned int seq64::perform::lookup_keyevent_key (int *seqnum*)

If we're not in legacy mode, then we adjust for the screenset, so that screensets greater than 0 can also show the correct key name, instead of a question mark.

Legacy seq24 already responds to the toggling of the mute state via the shortcut keys even if screenset $>$ 0, but it shows the question mark.

Parameters

seqnum	The number of the sequence for which to return the event key.

Returns

Returns the desired key. If there is no such value, then the period ('?') character is returned.

12.50.3.119 long seq64::perform::lookup_keyevent_seq (unsigned int *keycode*) [inline]

The inverse of lookup_keyevent_key().

Parameters

keycode	The number of the event key for which to return the configured sequence number.

Returns

Returns the desired sequence. If there is no such value, then a sequence number of 0 is returned.

12.50.3.120 unsigned int seq64::perform::lookup_keygroup_key (long *groupnum*) [inline]

Parameters

groupnum	The number of the sequence for which to return the group key.

Returns

Returns the desired key. If there is no such value, then the period ('.') character is returned.

12.50.3.121 long seq64::perform::lookup_keygroup_group (unsigned int *keycode*) [inline]

The inverse of lookup_keygroup_key().

Parameters

keycode	The number of the group key for which to return the configured sequence number.

Returns

Returns the desired group number. If there is no such value, then a group number of 0 is returned.

12.50.3.122 void seq64::perform::start_playing (bool *songmode* = `false`)

We've reversed the start() and start_jack() calls so that JACK is started first, to match all of the other use-cases for playing that we've found in the code. Note that the complementary function, stop_playing(), is an inline function defined in the header file.

Note

It would be nice to know why the following code snippet disables the mute/unmute functionality of the performance/song editor:

```
    position_jack(false);
    start_jack();
    start(false);


The jack_assistant::position() function doesn't use the boolean
parameter at present; that code is effectively disabled.  Okay, now it
does, if the "relocate" parameter is true.  See
perform::position_jack() and jack_assistant::position().  This
parameter, when true, allows the "klick" application to get proper
position data.

The perform::start() function passes its boolean flag to
perform::inner_start(), which sets the playback mode to that flag; if
that flag is false, that turns off "song" mode.  So that explains why
mute/unmute is disabled.
```

Parameters

songmode	Indicates if the caller wants to start the playback in JACK mode. In the seq42 (yes, "42", not "24") code at GitHub, this flag was identical to the "global_jack_start_mode" flag, which is true for Song mode, and false for Live mode. False disables Song mode, and is the default, which matches seq24. If the previous state was "paused", then we start it in Live mode, which works because Song mode has already turned on the sequences. This method is not quite intuitive, because it is really following Live mode.

12.50.3.123 void seq64::perform::pause_playing ( )

Currently almost the same as stop_playing(), but expanded as noted in the comments so that we ultimately have more granular control over what happens. We're researching the whole sequence of stopping and starting, and it can be tricky to make correct changes.

We still need to make restarting pick up at the same place in ALSA mode; in JACK mode, JACK transport takes care of that feature.

12.50.3.124 void seq64::perform::stop_playing ( )

Stops playback, turns off the (new) m_is_paused flag, and set the "is-pattern-playing" flag to false. With stop, reset the start-tick to either the left-tick or the 0th tick (to be determined, currently resets to 0)..

12.50.3.125 void seq64::perform::start_key (bool *songmode* = `false`)

Meant to be used by GUIs to unify the treatment of keys versus buttons.

Parameters

songmode	The live/play mode parameter to be passed along to the key processor. Defaults to false (live mode).

12.50.3.126 void seq64::perform::pause_key (bool *songmode* = `false`)

Meant to be used by GUIs to unify the treatment of keys versus buttons.

Parameters

songmode	The live/play mode parameter to be passed along to the key processor, when starting playback. Defaults to false (live mode).

12.50.3.127 void seq64::perform::stop_key ( )

Meant to be used by GUIs to unify the treatment of keys versus buttons.

12.50.3.128 void seq64::perform::learn_toggle ( ) `[inline]`

12.50.3.129 int seq64::perform::decrement_beats_per_minute ( ) `[inline]`

Actually does a lot of work in those function calls.

12.50.3.130 int seq64::perform::increment_beats_per_minute ( ) `[inline]`

Actually does a lot of work in those function calls.

12.50.3.131 int seq64::perform::decrement_screenset ( ) `[inline]`

12.50.3.132 int seq64::perform::increment_screenset ( ) `[inline]`

12.50.3.133 bool seq64::perform::highlight (const sequence & *seq*) const `[inline]`

This setting is currently a build-time option, but could be made a run-time option later.

Parameters

seq	Provides a reference to the desired sequence.

12.50.3.134 bool seq64::perform::is_smf_0 (const sequence & *seq*) const [inline]

Parameters

seq	Provides a reference to the desired sequence.

12.50.3.135 void seq64::perform::sequence_key (int *seq*)

This function is use in mainwnd when toggling the mute/unmute setting using keyboard keys.

Parameters

seq	The sequence's control-key number, which is relative to the current screen-set.

12.50.3.136 std::string seq64::perform::sequence_label (const sequence & *seq*)

This string goes on the bottom-left of those user-interface elements.

The format of this string is something like the following example, depending on the "show sequence numbers" option. The values shown are, in this order, sequence number (if allowed), buss number, channel number, beats per bar, and beat width.

```
No sequence number:     31-16 4/4
Sequence number:        9  31-16 4/4
```

```
The sequence number and buss number are re 0, while the channel number is
displayed re 1, unless it is an SMF 0 null channel (0xFF), in which case
it is 0.
```

Note

Later, we could add the sequence hot-key to this string, though showing that is not much use in perfnames. Also, this function is a stilted mix of direct access and access through sequence number.

Parameters

seq	Provides the reference to the sequence, use for getting the sequence parameters to be written to the label string.

Returns

Returns the filled in label if the sequence is active. Otherwise, an empty string is returned.

12.50.3.137 void seq64::perform::set_input_bus (int *bus,* bool *active*)

This function is called by options::input_callback().

Tricky Code See the bus parameter. We should provide two separate functions for this feature, but it is already combined into one input-callback function with a lot of other functionality in the options module.

Parameters

bus	If this value is greater than SEQ64_DEFAULT_BUSS_MAX (32), then it is treated as a user-interface flag (PERFORM_KEY_LABELS_ON_SEQUENCE or PERFORM_NUM_LABELS_ON_SEQUENCE) that causes all the sequences to be dirtied, and thus get redrawn with the new user-interface setting.
active	Indicates whether the buss or the user-interface feature is active or inactive.

12.50.3.138 bool seq64::perform::mainwnd_key_event (const keystroke & *k*)

This function handles the keys for the functions of replace, queue, keep-queue, snapshots, toggling mute groups, group learn, and playing screenset. For further keystroke processing, see mainwnd :: on_key_press_event().

Keys not handled here are handled in mainwnd: bpm up & down; screenset up & down.

Parameters

k	The keystroke object to be handled.

Returns

Returns true if the key was handled.

12.50.3.139 bool seq64::perform::perfroll_key_event (const keystroke & *k,* int *drop_sequence*)

It handles the Ctrl keys for cut, copy, paste, and undo.

The "is modified" flag is raised if something is deleted, but we cannot yet handle the case where we undo all the changes. So, for now, we play it safe with the user, even if the user gets annoyed because he knows that he undid all the changes.

Parameters

k	The keystroke object to be handled.
drop_sequence	Provides the index of the sequence whose selected trigger is to be cut, copied, or pasted. (Undo not yet supported).

Returns

Returns true if the key was handled.

12.50.3.140 bool seq64::perform::playback_key_event (const keystroke & *k*, bool *songmode* = false)

To be used in mainwnd, perfedit, and seqroll.

The start/end key may be the same key (e.g. Space) to allow toggling when the same key is mapped to both triggers.

Checking is_running() may not work completely in JACK.

Parameters

k	Provides the encapsulated keystroke to check.
songmode	Provides the "jack flag" needed by the mainwnd, seqroll, and perfedit windows. Defaults to false, which disables Song mode, and enables Live mode. But using Song mode seems to make the pause key not work in the performance editor.

Returns

Returns true if the keystroke matched the start, stop, or (new) pause keystrokes. Generally, no further keystroke processing is needed in this case.

12.50.3.141 int seq64::perform::max_active_set ( ) const [private]

Returns

Returns the value of the highest active set. A value of 0 represents the first set. If no sequences are active, then -1 is returned.

12.50.3.142 void seq64::perform::launch_input_thread ( ) [private]

This might be a good candidate for a small thread class derived from a small base class.

12.50.3.143 void seq64::perform::launch_output_thread ( ) [private]

This might be a good candidate for a small thread class derived from a small base class.

12.50.3.144 bool seq64::perform::init_jack ( ) [inline], [private]

Who calls this routine? The main() routine of the application [via launch()], and the options module, when the Connect button is pressed.

Returns

Returns the result of the init() call; true if JACK sync is now running. If JACK support is not built into the application, then this function returns false, to indicate that JACK is (definitely) not running.

12.50.3.145 bool seq64::perform::deinit_jack ( ) [inline], [private]

Called by launch() and in the options module, when the Disconnect button is pressed.

Returns

Returns the result of the init() call; false if JACK sync is now no longer running. If JACK support is not built into the application, then this function returns true, to indicate that JACK is (definitely) not running.

12.50.3.146 bool seq64::perform::seq_in_playing_screen (int *seq*) [private]

Parameters

seq	Provides the index of the desired sequence.

Returns

Returns true if the sequence adheres to the conditions noted above.

12.50.3.147 void seq64::perform::is_modified (bool *flag*) [inline], [private]

Parameters

flag	The value of the modified flag to be set.

12.50.3.148 bool seq64::perform::is_midi_control_valid (int *seq*) const [inline], [private]

Parameters

seq	The value that should be in the c_midi_controls range.

Returns

Returns true if the parameter is valid. For this function, no error print-out is generated.

12.50.3.149 bool seq64::perform::is_screenset_valid (int *screenset*) const [inline], [private]

Parameters

screenset	The prospective screenset value.

Returns

Returns true if the parameter is valid. For this function, no error print-out is generated.

12.50.3.150 void seq64::perform::set_running (bool *running*) [inline], [private]

Parameters

running	The value of the running flag to be set.

12.50.3.151 void seq64::perform::set_playback_mode (bool *playbackmode*) [inline], [private]

Parameters

playbackmode	The value of the playback mode flag to be set.

12.50.3.152 int seq64::perform::mute_group_offset (int *track*) [inline], [private]

Parameters

track	The number of the desired track.

12.50.3.153 bool seq64::perform::is_seq_valid (int *seq*) const [private]

Also see the function is_mseq_valid(), which also checks the pointer stored in the m_seq[] array.

We considered checking the *seq* param against sequence_count(), but this function is called while creating sequences that add to that count, so we continue checking against the "container" size. Also, it is possible to have holes in the array representing inactive sequences, so that sequencer_count() would be too limiting.

Parameters

seq	The sequencer number, in interval [0, m_sequence_max).

Returns

Returns true if the sequence number is valid.

12.50.3.154 bool seq64::perform::is_mseq_valid (int *seq*) const [private]

It also evaluates the m_seq[seq] pointer value.

Note

Since we can have holes in the sequence array, where there are inactive sequences, we check if the sequence is even active before emitting a message about a null pointer for the sequence. We only want to see messages that indicate actual problems.

Parameters

seq	Provides the sequence number to be checked. It is checked for validity. We cannot compare the sequence number versus the sequence_count(), because the current implementation can have inactive holes (with null pointers) interspersed with active pointers.

Returns

Returns true if the sequence number is valid as per is_seq_valid(), and the sequence pointer is not null.

12.50.3.155 bool seq64::perform::install_sequence (sequence * *seq*, int *seqnum*) [private]

It is common code and using it prevents inconsistences. It assumes values have already been checked. It does not set the "is modified" flag, since adding a sequence by loading a MIDI file should not set it. Compare new_↩ sequence(), used by mainwid and seqmenu, with add_sequence(), used by midifile.

Parameters

seq	The pointer to the pattern/sequence to add.
seqnum	The sequence number of the pattern to be added. Not validated, to save some time.

Returns

Returns true if a sequence was removed, or the sequence was successfully added. In other words, if a real change in sequence pointers occurred. It is up to the caller to decide if the change warrants setting the "is modified" flag.

12.50.3.156 void seq64::perform::inner_start (bool *state*) [private]

Then, if not is_running(), the playback mode is set to the given state. If that state is true, call off_sequences(). Set the running status, and signal the condition. Then unlock.

Minor issue:

```
In ALSA mode, restarting the sequence moves the progress bar to the
beginning of the sequence, even if just pausing.  This is fixed by
compiling with SEQ64_PAUSE_SUPPORT, which disables calling
off_sequences() when starting playback from the song editor /
performance window.  WE STILL HAVE TO EVALUATE WHAT SIDE-EFFECTS MIGHT
OCCUR.  ALSO CONSIDER A RUN-TIME --pause-support option for this
feature.
```

Parameters

state	Sets the playback mode, and, if true, turns off all of the sequences.

12.50.3.157 void seq64::perform::inner_stop ( ) [private]

Note that we do need to set the running flag to false here, even when JACK is running. Otherwise, JACK starts ping-ponging back and forth between positions under some circumstances.

However, if JACK is running, we do not want to reset the sequences... this causes the progress bar for each sequence to remove to near the end of the sequence.

12.50.3.158 int seq64::perform::clamp_track (int *track*) const [private]

Fixed the bug we found, where we checked for track > m_seqs_in_set, instead of using the >= operator.

Parameters

track	The track value to be checked and rectified as necessary.

Returns

Returns the track parameter, clamped between 0 and m_seqs_in_set-1, inclusive.

12.50.3.159 void seq64::perform::set_all_key_events ( ) [inline], [private]

12.50.3.160 void seq64::perform::set_all_key_groups ( ) [inline], [private]

12.50.3.161 void seq64::perform::set_key_event (unsigned int *keycode,* long *sequence_slot*) [inline], [private]

It is called 32 times, corresponding to the pattern/sequence slots in the Patterns window. It first removes the given key-code from the regular and reverse slot-maps. Then it removes the sequence-slot from the regular and reverse slot-maps. Finally, it adds the sequence-slot with a key value of key-code, and adds the key-code with a value of sequence-slot.

Parameters

keycode	The keycode for which to set the sequence slot.
sequence_slot	The sequence slot to be set.

12.50.3.162 void seq64::perform::set_key_group (unsigned int *keycode,* long *group_slot*) [inline], [private]

It is called 32 times, corresponding the pattern/sequence slots in the Patterns window. Compare it to the set_key↩ _events() function.

Parameters

keycode	The keycode for which to set the group slot.
group_slot	The group slot to be set.

12.50.4 Friends And Related Function Documentation

12.50.4.1 friend class jack_assistant [friend]

12.50.4.2 friend class keybindentry [friend]

12.50.4.3 friend class midifile [friend]

12.50.4.4 friend class optionsfile [friend]

12.50.4.5 friend class options [friend]

12.50.4.6 int jack_sync_callback (jack_transport_state_t *state*, jack_position_t * *pos*, void * *arg*) [friend]

This JACK synchronization callback informs the specified perform object of the current state and parameters of JACK.

The transport state will be:

```
-   JackTransportStopped when a new position is requested.
-   JackTransportStarting when the transport is waiting to start.
-   JackTransportRolling when the timeout has expired, and the
    position is now a moving target.
```

Parameters

state	The JACK Transport state.
pos	The JACK position value.
arg	The pointer to the jack_assistant object. Currently not checked for nullity, nor dynamic-casted.

Returns

Returns 1 if the function works, and 0 if something was wrong.

12.50.5 Field Documentation

12.50.5.1 midi_control seq64::perform::sm_mc_dummy [static], [private]

Instantiate the dummy midi_control object, which is used in lieu of a null pointer.

We're taking code that basically works already, in the sense that it never seems to access a null pointer. So we're not even risking data transfers between this dummy object and the ones we really want to use.

12.50.5.2 gui_assistant& seq64::perform::m_gui_support [private]

12.50.5.3 bool seq64::perform::m_mute_group[c_gmute_tracks] [private]

This value determines whether a particular track will be muted or unmuted, and it can handle all tracks available in the application (currently 1024). Note that the current state of playing can be "learned", and stored herein as the desired state for the track.

12.50.5.4 bool seq64::perform::m_tracks_mute_state[c_seqs_in_set] [private]

Unlike the m_mute_group[] array, this holds the current state, rather than the state desired by activating a mute group, and it applies to only one screen-set.

12.50.5.5 bool seq64::perform::m_mode_group [private]

This value starts out true. It is altered by the c_midi_control_mod_gmute handler or when the keys().group_off() or the keys().group_on() keys are struck.

12.50.5.6 bool seq64::perform::m_mode_group_learn [private]

12.50.5.7 int seq64::perform::m_mute_group_selected [private]

It seems like a "group" is essentially a "set" that is selected for the saving and restoring of the status of all patterns in that set.

12.50.5.8 int seq64::perform::m_playing_screen [private]

In seq24, this value is altered by set_playing_screenset(), which is called by handle_midi_control(c_midi_control↩ _play_ss, state).

12.50.5.9 int seq64::perform::m_playscreen_offset [private]

Saves some multiplications, should make the code easier to grok, and centralizes the use of c_seqs_in_set, which we want to be able to change at run-time, as a future enhancement.

12.50.5.10 sequence* seq64::perform::m_seqs[c_max_sequence] [private]

Todo First, make the sequence array a vector, and second, put allof these flags into a structure and access those members indirectly.

12.50.5.11 bool seq64::perform::m_seqs_active[c_max_sequence] [private]

This array can have "holes" with inactive sequences, so every sequence needs to be checked before using it.

12.50.5.12 bool seq64::perform::m_was_active_main[c_max_sequence] [private]

This value seems to be used only in maintaining dirtiness-status; did some process modify the sequence? Was it's mute/unmute status changed?

12.50.5.13 bool seq64::perform::m_was_active_edit[c_max_sequence] [private]

This value seems to be used only in maintaining dirtiness-status for editing the mute/unmute status during pattern editing.

12.50.5.14 bool seq64::perform::m_was_active_perf[c_max_sequence] [private]

This value seems to be used only in maintaining dirtiness-status for editing the mute/unmute status during performance/song editing.

12.50.5.15 bool seq64::perform::m_was_active_names[c_max_sequence] [private]

This value seems to be used only in maintaining dirtiness-status for editing the mute/unmute status during performance names editing. Not sure that it serves a real purpose; perhaps created with an eye to editing the pattern name in the song editor?

12.50.5.16 bool seq64::perform::m_sequence_state[c_max_sequence] [private]

12.50.5.17 mastermidibus seq64::perform::m_master_bus [private]

12.50.5.18 pthread_t seq64::perform::m_out_thread [private]

Provides a "handle" to the output thread.

12.50.5.19 pthread_t seq64::perform::m_in_thread [private]

12.50.5.20 bool seq64::perform::m_out_thread_launched [private]

12.50.5.21 bool seq64::perform::m_in_thread_launched [private]

12.50.5.22 bool seq64::perform::m_running [private]

12.50.5.23 bool seq64::perform::m_inputing [private]

12.50.5.24 bool seq64::perform::m_outputing [private]

12.50.5.25 bool seq64::perform::m_looping [private]

If true, the performance will loop between the L and R markers in the performance editor.

12.50.5.26 bool seq64::perform::m_playback_mode [private]

There are two, "live" and "song", indicated by the following values:

```
m_playback_mode == false:       live mode
m_playback_mode == true:        playback/song mode
```

12.50.5.27 int seq64::perform::m_ppqn [private]

12.50.5.28 int seq64::perform::m_beats_per_bar [private]

The default value is SEQ64_DEFAULT_BEATS_PER_MEASURE (4).

12.50.5.29 int seq64::perform::m_beat_width [private]

The default value is SEQ64_DEFAULT_BEAT_WIDTH (4).

12.50.5.30 midipulse seq64::perform::m_one_measure [private]

We can save some multiplications, and, more importantly, later define a more flexible definition of "one measure's worth" than simply four quarter notes.

12.50.5.31 midipulse seq64::perform::m_left_tick [private]

Note that "tick" is actually "pulses".

12.50.5.32 midipulse seq64::perform::m_right_tick [private]

Note that "tick" is actually "pulses".

12.50.5.33 midipulse seq64::perform::m_starting_tick [private]

By default, this value is always reset to the value of the "left tick". We want to eventually be able to leave it at the last playing tick, to support a "pause" functionality. Note that "tick" is actually "pulses".

12.50.5.34 midipulse seq64::perform::m_tick [mutable], [private]

The m_tick member holds the tick to be used in displaying the progress bars and the maintime pill. It is mutable because sometimes we want to adjust it in a const function for pause functionality.

12.50.5.35 midipulse seq64::perform::m_jack_tick [private]

12.50.5.36 bool seq64::perform::m_usemidiclock [private]

12.50.5.37 bool seq64::perform::m_midiclockrunning [private]

12.50.5.38 int seq64::perform::m_midiclocktick [private]

12.50.5.39 int seq64::perform::m_midiclockpos [private]

12.50.5.40 bool seq64::perform::m_is_paused [private]

12.50.5.41 std::string seq64::perform::m_screen_set_notepad[c_max_sets] [private]

12.50.5.42 midi_control seq64::perform::m_midi_cc_toggle[c_midi_controls] [private]

12.50.5.43 midi_control seq64::perform::m_midi_cc_on[c_midi_controls] [private]

12.50.5.44 midi_control seq64::perform::m_midi_cc_off[c_midi_controls] [private]

12.50.5.45 int seq64::perform::m_offset [private]

It is used in the MIDI control of the playback status of the sequences in the current screen-set. It is also used to offset the sequence numbers so that the control (mute/unmute) keys can be shown on any screen-set.

12.50.5.46 int seq64::perform::m_control_status [private]

Need to learn more about this one. It is used in the replace, snapshot, and queue functionality.

12.50.5.47 int seq64::perform::m_screenset [private]

This is merely the screen-set that is in view. The fix of tdeagan substitutes the "in-view" screen-set for the "playing" screen-set.

12.50.5.48 int seq64::perform::m_seqs_in_set [private]

This change will require some arrays to be dynamically allocated (vectors).

12.50.5.49 int seq64::perform::m_max_sets [private]

Again, currently set to the old value, which is used in hard-wired array sizes. To make it variable will require a move from arrays to vectors.

12.50.5.50 int seq64::perform::m_sequence_count [private]

Used by the install_sequence() function. Note that this value is not a suitable replacement for c_max_sequence/m↩
_sequence_max, because there can be inactive sequences amidst the active sequences.

12.50.5.51 int seq64::perform::m_sequence_max [private]

However, this value is already 32 ∗ 32 = 1024, and is probably enough for any usage. Famous last words?

12.50.5.52 int seq64::perform::m_edit_sequence [private]

Moving this status from seqmenu into perform for better centralized management.

12.50.5.53 bool seq64::perform::m_is_modified [private]

All the GUIs seem to use a perform object.

12.50.5.54 condition_var seq64::perform::m_condition_var [private]

It is signalled if playback has been started. The output thread function waits on this variable until m_running and m_outputing are false. This variable is also signalled in the perform destructor.

12.50.5.55 jack_assistant seq64::perform::m_jack_asst [private]

12.50.5.56 std::vector<performcallback ∗> seq64::perform::m_notify [private]

12.51 seq64::performcallback Struct Reference

Provides for notification of events.

Inheritance diagram for seq64::performcallback:



Public Member Functions

- virtual void on_grouplearnchange (bool)

  A do-nothing callback.

12.51.1 Detailed Description

Provide a response to a group-learn change event.

12.51.2 Member Function Documentation

12.51.2.1 virtual void seq64::performcallback::on_grouplearnchange (bool) [inline], [virtual]

"state" is an Unused parameter.

Reimplemented in seq64::mainwnd.

12.52 seq64::perfroll Class Reference

This class implements the performance roll user interface.

Inheritance diagram for seq64::perfroll:



Public Member Functions

- perfroll (perform &perf, perfedit &parent, Gtk::Adjustment &hadjust, Gtk::Adjustment &vadjust, int ppqn=S↩ EQ64_USE_DEFAULT_PPQN)

  Principal constructor.

- virtual ~perfroll ()

  This destructor deletes the interaction object.

- void set_guides (int snap, int measure, int beat)

  This function sets the m_snap, m_measure_length, and m_beat_length members directly from the function parameters, which are in units of pulses (sometimes misleadingly called "ticks".)
- void update_sizes ()

  Updates the sizes of various items.
- void init_before_show ()

  Sets the roll-lengths ticks member.
- void fill_background_pixmap ()

  This function updates the background of the piano roll.
- void increment_size ()

  Increments the value of m_roll_length_ticks by the PPQN ∗ 512, then calls update_sizes().
- void draw_all ()

  Provides a very common sequence of calls used in perfroll_input.
- void follow_progress ()
- void redraw_progress ()

  Helper function to simplify the client call.

Private Member Functions

- void draw_progress ()

  Draws the progress line that shows where we are in the performance.
- void redraw_dirty_sequences ()

  Redraws patterns/sequences that have been modified.
- void set_ppqn (int ppqn)

  Handles changes to the PPQN value in one place.
- void convert_xy (int x, int y, midipulse &ticks, int &seq)

  Converts (x, y) coordinates on the piano roll to tick (pulse) and sequence numbers.
- void convert_x (int x, midipulse &ticks)

  Converts a tick-offset on the x coordinate.
- void snap_x (int &x)

  This function performs a 'snap' action on x.
- void draw_sequence_on (int seqnum)

  Draws the given pattern/sequence on the given drawable area.
- void draw_background_on (int seqnum)

  Draws the given pattern/sequence background on the given drawable area.
- void draw_drawable_row (long y)

  Not quite sure what this draws yet.
- void change_horz ()

  Changes the 4-bar horizontal offset member and queues up a draw operation.
- void change_vert ()

  Changes the 4-bar vertical offset member and queues up a draw operation.
- void split_trigger (int sequence, midipulse tick)

  Splits a trigger, whatever that means.
- void enqueue_draw ()

  Wraps queue_draw() and forwards the call to the parent perfedit, so that it can forward it to any other perfedit that exists.
- void set_zoom (int z)

  Implements the horizontal zoom feature.
- void horizontal_adjust (double step)

  This function provides optimization for the on_scroll_event() function.

- void vertical_adjust (double step)

  This function provides optimization for the on_scroll_event() function.
- void horizontal_set (double value)

  Sets the exact position of a horizontal scroll-bar.
- void vertical_set (double value)

  Sets the exact position of a vertical scroll-bar.
- void on_realize ()

  Provides the on-realization callback.
- bool on_expose_event (GdkEventExpose ∗ev)

  Handles the on-expose event.
- bool on_button_press_event (GdkEventButton ∗ev)

  This callback function handles a button press by forwarding it to the interaction object's button-press function.
- bool on_button_release_event (GdkEventButton ∗ev)

  This callback function handles a button release by forwarding it to the interaction object's button-release function.
- bool on_motion_notify_event (GdkEventMotion ∗ev)

  Handles motion notification by forwarding it to the interaction object's motion-notification callback function.
- bool on_scroll_event (GdkEventScroll ∗ev)

  Handles horizontal and vertical scrolling.
- bool on_focus_in_event (GdkEventFocus ∗ev)

  This callback handles an in-focus event by setting the flag to HAS_FOCUS.
- bool on_focus_out_event (GdkEventFocus ∗ev)

  This callback handles an out-of-focus event by resetting the flag HAS_FOCUS.
- void on_size_allocate (Gtk::Allocation &al)

  Upon a size allocation event, this callback calls the base-class version of this function, then sets m_window_x and m_window_y, and calls update_sizes().
- bool on_key_press_event (GdkEventKey ∗ev)

  This callback function handles a key-press event.
- void on_size_request (GtkRequisition ∗)

  This do-nothing callback effectively throws away a size request.

Private Attributes

- perfedit & m_parent

  Provides a link to the perfedit that created this object.
- int m_h_page_increment

  Provides the horizontal page increment for the horizontal scrollbar.
- int m_v_page_increment

  Provides the vertical page increment for the vertical scrollbar.
- int m_snap

  The amount of horizontal snap.
- int m_ppqn

  Parts-per-quarter-note value.
- int m_page_factor

  4096, horizonal page sizing.
- int m_divs_per_beat

  Holds current tick scaling value.
- int m_ticks_per_bar

  Holds current bar scaling value.
- int m_perf_scale_x

  Scaling based on zoom and PPQN.

- int m_zoom

  New value to attempt a rudimentary time-zoom feature.
- int m_names_y

  The maximum height of the perfroll names box, in pixes.
- int m_background_x

  The width of the perfroll background.
- int m_size_box_w

  This is a basically constant value set to s_perfroll_size_box_w = 3.
- int m_measure_length

  The legnth of a measure, in beat units.
- int m_beat_length

  The length of a beat, in parts-per-quarter note.
- midipulse m_old_progress_ticks

  Saves the position of the progress bar, for erasing it in preparation for drawing it at the next tick value.
- int m_4bar_offset

  Holds the horizontal offset related to the horizontal scroll-bar position.
- int m_sequence_offset

  This value is the vertical version of m_4bar_offset.
- int m_roll_length_ticks

  Provides the width of the piano roll in ticks.
- midipulse m_drop_tick

  The horizontal location for section movement.
- midipulse m_drop_tick_trigger_offset

  The horizontal trigger location for section movement.
- int m_drop_sequence

  Holds the currently-selected sequence being moved.
- int m_sequence_max

  Currently, just a class-specific version of c_max_sequence, meant for the future.
- bool m_sequence_active [c_max_sequence]

  Used when drawing an active sequence.
- FruityPerfInput m_fruity_interaction

  We need both styles of interaction object present.
- Seq24PerfInput m_seq24_interaction

  Provides support for standard Seq24 mouse handling, plus the keystroke handlers.
- bool m_moving

  Used in the Seq24 or Fruity processing when moving a section of triggers.
- bool m_growing

  Used in the Seq24 or Fruity processing when growing a section of triggers.
- bool m_grow_direction

  Used in the Seq24 or Fruity processing when growing a section of triggers.

Friends

- class FruityPerfInput

  These friend implement interaction-specific behavior, although only the Seq24 interactions support full keyboard processing, except for some common functionality provided by perform::perfroll_key_event().
- class Seq24PerfInput
- class perfedit

Additional Inherited Members

12.52.1 Constructor & Destructor Documentation

12.52.1.1 seq64::perfroll::perfroll (perform & *perf*, perfedit & *parent*, Gtk::Adjustment & *hadjust*, Gtk::Adjustment & *vadjust*, int *ppqn* = SEQ64_USE_DEFAULT_PPQN)

12.52.1.2 seq64::perfroll::~perfroll ( ) [virtual]

Well, now there are two objects, so no explicit deletion necessary.

12.52.2 Member Function Documentation

12.52.2.1 void seq64::perfroll::set_guides (int *snap*, int *measure*, int *beat*)

This function then fills in the background, and queues up a draw operation.

Parameters

snap	Provides the number of snap-pulses (pulses per snap interval) as calculated in perfedit::set_guides(). This is actually equal to the measure-pulses divided by the snap value in perfedit; the snap value defaults to 8.
measure	Provides the number of measure-pulses (pulses per measure) as calculated in perfedit::set_guides().
beat	Provides the number of beat-pulses (pulses per beat) as calculated in perfedit::set_guides().

12.52.2.2 void seq64::perfroll::update_sizes ( )

Note

Trying to figure out what the 16 is. So take the "bars-visible" calculation, the c_perf_scale_x value, assume that "ticks" is another name for "pulses", and assume that "beats" is a quarter note. Ignoring the numbers, the units come out to:

```
        pixels * ticks / pixel
bars = --------------------------------
        ticks / beat * beats / bar
```

```
Thus, the 16 is a "beats per bar" or "beats per measure" value.
This doesn't quite make sense, but there are 16 divisions per
beat on the perfroll user-interface.  So for now we'll call it
the latter, and make a variable called "m_divs_per_beat", see its
definition in the class initializer list.
```

12.52.2.3 void seq64::perfroll::init_before_show ( )

First, it gets the largest trigger value among the active sequences. Then it truncates this value to the nearest PPQN $*$ 16 ticks. Then it adds PPQN $*$ 4096 ticks.

12.52.2.4 void seq64::perfroll::fill_background_pixmap ( )

The first thing done is to clear the background by painting it with a filled white rectangle.

This function is called whenever something occurs (e.g. zoom) that can affect how the piano roll is drawn.

12.52.2.5 void seq64::perfroll::increment_size ( )

12.52.2.6 void seq64::perfroll::draw_all ( )

12.52.2.7 void seq64::perfroll::follow_progress ( )

12.52.2.8 void seq64::perfroll::redraw_progress ( ) [inline]

12.52.2.9 void seq64::perfroll::draw_progress ( ) [private]

We would like to be able to leave the line there when the progress is paused while running off of JACK transport. How? The perf().get_tick() call always returns 0 when stop is in force.

If we comment out the erasure of the old line, we see that the progress bar is also erased when a pattern boundary is hit (triggers), and when the sequence is stopped by the user.

In order to support true pause in the song editor, we tried to replace perform::get_tick() with perform::get_start_tick() and perform::get_last_tick() [a new experimental function]. But those replacements here always return 0, even as perform::get_tick() increases. Now were are trying a newer function, perform::get_max_tick(), which seems to do the trick for resuming (instead of rewinding) the progress bar. It's still a tiny bit laggy, so we have to find a faster way to get the maximum. (Note that the draw_progress function is called at every timeout, that is, constantly.)

The perform::get_max_tick() call doesn't work with JACK: the progress bar rewinds to the beginning when playback is paused, though it does resume where it left off. It also may cause the progress bar to backtrack through any gap. Let's restore the get_tick() call.

12.52.2.10 void seq64::perfroll::redraw_dirty_sequences ( ) [private]

Change Note ca 2016-05-30 Lets try not drawing sequences greater than the maximum, at all.

12.52.2.11 void seq64::perfroll::set_ppqn (int *ppqn*) [private]

The m_ticks_per_bar member replaces the global ppqn times 16. This construct is parts-per-quarter-note times 4 quarter notes times 4 sixteenth notes in a bar. (We think...)

The m_perf_scale_x member starts out at c_perf_scale_x, which is 32 ticks per pixel at the default tick rate of 192 PPQN. We adjust this now. But note that this calculation still involves the c_perf_scale_x constant.

Todo Resolve the issue of c_perf_scale_x versus m_perf_scale_x in perfroll.

12.52.2.12 void seq64::perfroll::convert_xy (int *x,* int *y,* midipulse & *d_tick,* int & *d_seq*) [private]

The results are returned via the d_tick and d_seq parameters. The sequence number is clipped to a legal value (0 to m_sequence_max).

Parameters

	x	The x coordinate of the mouse pointer.
	y	The y coordinate of the mouse pointer.
out	*d_tick*	Holds the calculated tick value.
out	*d_seq*	Holds the calculated sequence-number value.

12.52.2.13 void seq64::perfroll::convert_x (int *x*, midipulse & *tick*) [private]

The result is returned via the tick parameter.

12.52.2.14 void seq64::perfroll::snap_x (int & *x*) [private]

- m_snap = number pulses to snap to
- m_perf_scale_x = number of pulses per pixel

Therefore mod = m_snap/m_perf_scale_x equals the number pixels to snap to.

12.52.2.15 void seq64::perfroll::draw_sequence_on (int *seqnum*) [private]

Statement nesting from hell!

12.52.2.16 void seq64::perfroll::draw_background_on (int *seqnum*) [private]

12.52.2.17 void seq64::perfroll::draw_drawable_row (long *y*) [private]

It is involved in the drawing of a greyed (selected) row.

What's weird is that we divide y by m_names_y, then multiply it by m_names_y, before passing the result to draw↩_drawable(). However, if we just as y casted to an int, then the drawing of the row is only partial, vertically.

12.52.2.18 void seq64::perfroll::change_horz ( ) [private]

Since the m_4bar_offset value is always multiplied by m_ticks_per_bar before usage, let's just do it here and not have to multiply it later.

12.52.2.19 void seq64::perfroll::change_vert ( ) [private]

12.52.2.20 void seq64::perfroll::split_trigger (int *sequence*, midipulse *tick*) [private]

12.52.2.21 void seq64::perfroll::enqueue_draw ( ) [private]

The parent perfedit will call perfroll::queue_draw() on behalf of this object, and it will pass a perfroll::enqueue_draw() to the peer perfedit's perfroll, if the peer exists.

12.52.2.22 void seq64::perfroll::set_zoom (int *z*) [private]

Change Note ca 2016-04-05 The initial zoom value is c_perf_scale_x (32). We allow it to range from 1 to 128, for now. Smaller values zoom in.

12.52.2.23 void seq64::perfroll::horizontal_adjust (double *step*) [inline], [private]

A duplicate of the one in seqroll.

Parameters

step	Provides the step value to use for adjusting the horizontal scrollbar. See gui_drawingarea_gtk2::scroll_hadjust() for more information.

12.52.2.24 void seq64::perfroll::vertical_adjust (double *step*) [inline], [private]

A near-duplicate of the one in seqroll.

Parameters

step	Provides the step value to use for adjusting the vertical scrollbar. See gui_drawingarea_gtk2::scroll_vadjust() for more information.

12.52.2.25 void seq64::perfroll::horizontal_set (double *value*) [inline], [private]

Parameters

value	The desired position. Mostly this is either 0.0 or 9999999.0 (an "infinite" value to select the start or end position.

12.52.2.26 void seq64::perfroll::vertical_set (double *value*) [inline], [private]

Parameters

value	The desired position. Mostly this is either 0.0 or 9999999.0 (an "infinite" value to select the start or end position.

12.52.2.27 void seq64::perfroll::on_realize ( ) [private]

Calls the base-class version first.

Then it allocates the additional resources need, that couldn't be initialized in the constructor, and makes some connections.

12.52.2.28 bool seq64::perfroll::on_expose_event (GdkEventExpose * *ev*) [private]

Draws a vertical page of the performance editor. The part drawn starts at m_sequence_offset and continues until the last sequence that can be at least partially seen given the height of the window.

If we're at the bottom of the sequences (1024, a non-existent sequence) would be the last sequence shown, we don't bother drawing it. This prevents debug messages about an illegal sequence, and can show a black bottom row that is a clear sign we're at the end of the legal sequences.

Parameters

ev	Provides the expose event.

Returns

Always returns true.

12.52.2.29 bool seq64::perfroll::on_button_press_event (GdkEventButton * *ev*) [private]

This gives us Seq24 versus Fruity behavior.

One minor issue: Fruity behavior doesn't yet provide the keystroke behavior we now handle for the Seq24 mode of operation.

12.52.2.30 bool seq64::perfroll::on_button_release_event (GdkEventButton * *ev*) [private]

This gives us Seq24 versus Fruity behavior.

12.52.2.31 bool seq64::perfroll::on_motion_notify_event (GdkEventMotion * *ev*) [private]

12.52.2.32 bool seq64::perfroll::on_scroll_event (GdkEventScroll * *ev*) [private]

If the Shift key is held while scrolling, then the scrolling is horizontal, otherwise it is vertical. This matches the convention of the seqedit class.

Note that, unlike the seqedit class, Ctrl-Scroll is not used to modify the zoom value. Rather than mess up legacy behavior, we will rely on keystrokes (z, 0, Z, and Ctrl-Page-Up and Ctrl-Page-Down) to implement this zoom.

Parameters

ev	Provides the scroll event.

Returns

Currently always returns true.

12.52.2.33 bool seq64::perfroll::on_focus_in_event (GdkEventFocus * *ev*) [private]

12.52.2.34 bool seq64::perfroll::on_focus_out_event (GdkEventFocus * *ev*) [private]

12.52.2.35 void seq64::perfroll::on_size_allocate (Gtk::Allocation & *al*) [private]

12.52.2.36 bool seq64::perfroll::on_key_press_event (GdkEventKey * *ev*) [private]

If we don't check the event type first, then the ev->keyval value is something weird like 65507. Note that we pass the functionality on to the perform::perfroll_key_event() function for the handling of delete, cut, copy, paste, and undo operations. If the keystroke is not handled by that function, then we handle it here.

Note that only the Seq24 input interaction object handles additional keystrokes not handled by the perfroll_key_↩ event() function.

The perfroll_key_event() call handles Del, Ctrl-X, Ctrl-C, Ctrl-V, and Ctrl-Z (which does nothing at present).

We've also added support for moving up and down in the piano roll (Up and Down arrows), paging up and down (Page-Up and Page-Down keys), paging left and right (Shift Page-Up and Page-Down), paging to top and bottom (Home and End), and paging to start and end (Shift Home and End).

The Keypad-End key is an issue on our ASUS "gaming" laptop. Whether it is seen as a "1" or an "End" key depends on an interaction between the Shift and the Num Lock key. Annoying, takes some time to get used to. Note that, even though we filter out the Ctrl key here, it still works for Ctrl-X (cut) and Ctrl-V (paste). For undo, the Undo button can be used, Ctrl-Z never worked in this view anyway.

Warning

We see that 'x' and 'z' are already handled in perfroll_key_event() if the Ctrl key was pressed. Be careful.

12.52.2.37 void seq64::perfroll::on_size_request (GtkRequisition *) [inline], [private]

12.52.3 Friends And Related Function Documentation

12.52.3.1 friend class FruityPerfInput [friend]

The perfedit class needs access to the private enqueue_draw() function.

12.52.3.2 friend class Seq24PerfInput [friend]

12.52.3.3 friend class perfedit [friend]

12.52.4 Field Documentation

12.52.4.1 perfedit& seq64::perfroll::m_parent [private]

We want to support two perfedit windows, but the children of perfedit will have to communicate changes requiring a redraw through the parent.

12.52.4.2 int seq64::perfroll::m_h_page_increment [private]

It was set to 1, the same as the step increment. That is too little. This value will be set to 4, for now. Might be a useful "user" configuration option.

12.52.4.3 int seq64::perfroll::m_v_page_increment [private]

It was set to 1, the same as the step increment. That is too little. This value will be set to 8, for now. Might be a useful "user" configuration option.

12.52.4.4 int seq64::perfroll::m_snap [private]

12.52.4.5 int seq64::perfroll::m_ppqn [private]

12.52.4.6 int seq64::perfroll::m_page_factor [private]

12.52.4.7 int seq64::perfroll::m_divs_per_beat [private]

12.52.4.8 int seq64::perfroll::m_ticks_per_bar [private]

12.52.4.9 int seq64::perfroll::m_perf_scale_x [private]

12.52.4.10 int seq64::perfroll::m_zoom [private]

It seems to work pretty well now.

12.52.4.11 int seq64::perfroll::m_names_y [private]

This is currently semantically a constant set to c_names_y = 24.

12.52.4.12 int seq64::perfroll::m_background_x [private]

This is based on the m_ppqn value and the value of c_perf_scale_x (or is m_perf_scale_x preferable?)

12.52.4.13 int seq64::perfroll::m_size_box_w [private]

It is used in drawing the short lines of the small box that sits at the top-left and bottom-right corners of each segment in the pattern editor. These can be used to lengthen and shorten a section in the song editor. We will increase this size, perhaps double it, to make it easier to grab.

12.52.4.14 int seq64::perfroll::m_measure_length [private]

12.52.4.15 int seq64::perfroll::m_beat_length [private]

12.52.4.16 midipulse seq64::perfroll::m_old_progress_ticks [private]

See the draw_progress() function. This could almost be static inside that function.

12.52.4.17 int seq64::perfroll::m_4bar_offset [private]

Used in drawing the progress bar and the sequence events. Also used in convert_x() and convert_xy(). This used to be the offset in units of bar ticks, but now we use it as a full-fledged ticks value. See the change_horz() function.

12.52.4.18 int seq64::perfroll::m_sequence_offset [private]

It is obtained or changed when the vertical scroll-bar moves. It is used for drawing the correct vertical window in the piano roll.

12.52.4.19 int seq64::perfroll::m_roll_length_ticks [private]

Calculated in init_before_show() based on the maximum trigger found in the perform object, the ticks/bar, the PPQN, and the page factor. Also can be increased in size in the increment_size() function [tied to the Grow button]. Used in update_sizes().

12.52.4.20 midipulse seq64::perfroll::m_drop_tick [private]

Used only by the friend modules perfroll_input and fruityperfroll_input.

12.52.4.21 midipulse seq64::perfroll::m_drop_tick_trigger_offset [private]

Used only by the friend modules perfroll_input and fruityperfroll_input.

12.52.4.22 int seq64::perfroll::m_drop_sequence [private]

Used for redrawing the sequence.

12.52.4.23 int seq64::perfroll::m_sequence_max [private]

12.52.4.24 bool seq64::perfroll::m_sequence_active[c_max_sequence] [private]

Not sure yet why we can't just use the sequence's member function to access this status boolean.

12.52.4.25 FruityPerfInput seq64::perfroll::m_fruity_interaction [private]

Even if the user specifies the fruity interaction, the Seq24 interaction is still needed to handle our new keystroke support for the perfroll. We need both objects to exist all the time, similar to the Fruity/Seq24 roles in the seqroll object.

Obsolete AbstractPerfInput * m_interaction

12.52.4.26 Seq24PerfInput seq64::perfroll::m_seq24_interaction [private]

12.52.4.27 bool seq64::perfroll::m_moving [private]

12.52.4.28 bool seq64::perfroll::m_growing [private]

12.52.4.29 bool seq64::perfroll::m_grow_direction [private]

Determines whether the section is growing to the left or to the right.

12.53 seq64::perftime Class Reference

This class implements drawing the piano time at the top of the "performance window" (the "song editor").

Inheritance diagram for seq64::perftime:



Public Member Functions

- perftime (perform &perf, perfedit &parent, Gtk::Adjustment &hadjust, int ppqn=SEQ64_USE_DEFAULT_P↩ PQN)

  Principal constructor.
- virtual ~perftime ()

  Let's provide a do-nothing virtual destructor.

- void reset ()
- void set_scale (int scale)
- void set_guides (int snap, int measure)

  Sets the m_snap value and the m_measure_length members directly from the function parameters, which are in units of pulses (sometimes misleadingly called "ticks".)
- void increment_size ()

  This function does nothing.

Private Member Functions

- void enqueue_draw ()

  Wraps queue_draw() and forwards the call to the parent perfedit, so that it can forward it to any other perfedit that exists.
- void set_zoom (int z)

  Implements the horizontal zoom feature.
- void draw_background ()

  Separated out the drawing done in on_expose_event(), so that it can be redone when the zoom changes.
- void draw_progress_on_window ()
- void change_horz ()

  Changes the m_4bar_offset and queues a draw operation.
- void set_ppqn (int ppqn)

  Handles changes to the PPQN value in one place.
- long tick_to_pixel (midipulse tick)

  Common calculation to convert a pulse/tick value to a perftime x value.
- midipulse pixel_to_tick (long pixel)

  The inverse of tick_to_pixel().
- int tick_offset ()

  Centralizes calculation of the tick offset of the time bar.
- void update_sizes ()

  This function does nothing.
- int idle_progress ()

  This function just returns true.
- void update_pixmap ()

  This function does nothing.
- void draw_pixmap_on_window ()

  This function does nothing.
- void on_realize ()

  Implements the on-realization event, then allocates some resources the could not be allocated in the constructor.
- bool on_expose_event (GdkEventExpose *ev)

  Implements the on-expose event.
- bool on_button_press_event (GdkEventButton *ev)

  Implement the button-press event to set the L and R ticks.
- void on_size_allocate (Gtk::Allocation &r)

  Implements a size-allocation event.
- bool on_button_release_event (GdkEventButton *)

  This button-release handler does nothing.
- bool key_press_event (GdkEventKey *ev)

  This callback function handles a key-press event.

Private Attributes

- perfedit & m_parent

  Provides a link to the perfedit that created this object.
- int m_4bar_offset

  Not yet sure exactly what this member represents.
- int m_tick_offset

  This member is m_4bar_offset times 16 times the current PPQN, to save some calculations and centralize this value.
- int m_ppqn

  The current value of PPQN, which we are trying to get to work everywhere, when PPQN is changed from the global ppqn = 192.
- int m_snap

  Snap value, starts out very small, equal to m_ppqn.
- int m_measure_length

  Provides the length of a measure in pulses or ticks.
- int m_left_marker_tick

  Holds the current location of the left (L) marker when arrow movement is in force.
- int m_right_marker_tick

  Holds the current location of the right (R) marker when arrow movement is in force.
- int m_perf_scale_x

  A class version of the global c_perf_scale_x factor.
- int m_timearea_y

  A class version of the global c_timerarea_y factor.

Friends

- class perfedit

Additional Inherited Members

12.53.1 Constructor & Destructor Documentation

12.53.1.1 seq64::perftime::perftime (perform & *p*, perfedit & *parent*, Gtk::Adjustment & *hadjust*, int *ppqn* = SEQ64_USE_DEFAULT_PPQN)

In the constructor you can only allocate colors; get_window() returns 0 because we have not been realized.

Note

Note that we still have to use a global constant in the base-class constructor; we cannot assign it to the corresponding member beforehand.

Parameters

p	Provides a reference to the main performance object of the application.
parent	Provides a reference to the object that contains this object, so that this object can tell the parent to queue up a drawing operation.
hadjust	Provides the horizontal scrollbar object needed so that perftime can respond to scrollbar cursor/thumb movement.
ppqn	An optional override of the default PPQN value for the application.

12.53.1.2 virtual seq64::perftime::~perftime ( ) [inline], [virtual]

12.53.2 Member Function Documentation

12.53.2.1 void seq64::perftime::reset ( )

12.53.2.2 void seq64::perftime::set_scale (int *scale*)

12.53.2.3 void seq64::perftime::set_guides (int *snap*, int *measure*)

This function then fills in the background, and queues up a draw operation.

Parameters

snap	Provides the number of snap-pulses (pulses per snap interval) as calculated in perfedit::set_guides(). This is actually equal to the measure-pulses divided by the snap value in perfedit; the snap value defaults to 8.
measure	Provides the number of measure-pulses (pulses per measure) as calculated in perfedit::set_guides().

12.53.2.4 void seq64::perftime::increment_size ( ) [inline]

Compare it to perfroll::increment_size().

12.53.2.5 void seq64::perftime::enqueue_draw ( ) [private]

The parent perfedit will call perftime::queue_draw() on behalf of this object, and it will pass a perftime::enqueue_draw() to the peer perfedit's perftime, if the peer exists.

12.53.2.6 void seq64::perftime::set_zoom (int *z*) [private]

Redraws the background if the new zoom checked out.

Parameters

z	Provides the zoom value, which is checked, and then copied into m_perf_scale_x.

12.53.2.7 void seq64::perftime::draw_background ( ) [private]

Note that m_measure_length == 0 will cause integer overflow.

12.53.2.8 void seq64::perftime::draw_progress_on_window ( ) [private]

12.53.2.9 void seq64::perftime::change_horz ( ) [private]

Again, uses the constant, 16 [now offloaded to the new tick_offset() function.].

12.53.2.10 void seq64::perftime::set_ppqn (int *ppqn*) [private]

It also modifies m_snap, m_measure_length (but always for four measures!), and m_tick_offset.

Todo We need make the 4 constant variable per the number of beats (quarter-notes) per bar, and also at least make 16 (4x4) a meaningful manifest constant.

Parameters

ppqn	The override value for the PPQN.

12.53.2.11 long seq64::perftime::tick_to_pixel (midipulse *tick*) [inline], [private]

Parameters

tick	The horizontal tick value to convert to an x pixel value, based on tick-offset and the x-scale.

Returns

Returns the x-pixel representing the time location parameter.

12.53.2.12 midipulse seq64::perftime::pixel_to_tick (long *pixel*) [inline], [private]

Parameters

pixel	The pixel value.

Returns

Returns the time value represented b the pixel.

12.53.2.13 int seq64::perftime::tick_offset ( ) [inline], [private]

Returns

Returns m_4bar_offset $*$ 16 $*$ m_ppqn.

12.53.2.14 void seq64::perftime::update_sizes ( ) [inline], [private]

12.53.2.15 int seq64::perftime::idle_progress ( ) [inline], [private]

12.53.2.16 void seq64::perftime::update_pixmap ( ) [inline], [private]

12.53.2.17 void seq64::perftime::draw_pixmap_on_window ( ) [inline], [private]

12.53.2.18 void seq64::perftime::on_realize ( ) [private]

It is important to call the base-class version of this function.

The former work of this function is now done in base-class's on_realize() and in its constructor now.

```
m_window = get_window();
m_gc = Gdk::GC::create(m_window);
m_window->clear();
set_size_request(10, m_timearea_y);
```

12.53.2.19 bool seq64::perftime::on_expose_event (GdkEventExpose * *ev*) [private]

Redraws the background.

Note

The perfedit object is created early on. When brought on-screen from mainwnd (the main window), first, perftime::on_realize() is called, then this event is called.

Parameters

ev	The expose event, not used.

Returns

Always returns true.

12.53.2.20 bool seq64::perftime::on_button_press_event (GdkEventButton * *p0*) [private]

Added functionality to try to set the start-tick if ctrl-left-click is pressed.

Parameters

p0	The button event.

Returns

Always returns true.

Why is setting the start-tick disabled? We re-enable it and see if it works. To our surprise, it works, but it sticks between stop/pause and the next playback in the performance editor. We added a feature where stop sets the start-tick to the left tick (or the beginning tick).

12.53.2.21 void seq64::perftime::on_size_allocate (Gtk::Allocation & *r*) [private]

12.53.2.22 bool seq64::perftime::on_button_release_event (GdkEventButton *) [inline], [private]

"ev", The button event parameter, is not used.

Returns

Always returns false

12.53.2.23 bool seq64::perftime::key_press_event (GdkEventKey * *ev*) [private]

Can't get the keystroke events to be seen by perfroll or perftime here using the normal callback function for keystrokes, and not sure why. The perfedit object can call this function, and that call works, so the perfedit class, which does get keystrokes, calls this function to do the work.

This function uses the "l" key to activate the movement of the "L" marker with the arrow keys, by the interval of on snap value for each press. It also uses the "r" key to activate the movement of the "R" marker, and the "x" to deactivate either movement move.

Be aware that there is no visual feedback, as yet, that one is in the movement mode.

Also be aware the changing the name of this function from "key_press_event()" to "on_key_press_event()" will disrupt the process, causing keystrokes to not get here. Too tricky.

12.53.3 Friends And Related Function Documentation

12.53.3.1 friend class perfedit [friend]

12.53.4 Field Documentation

12.53.4.1 perfedit& seq64::perftime::m_parent [private]

We want to support two perfedit windows, but the children of perfedit will have to communicate changes requiring a redraw through the parent.

12.53.4.2 int seq64::perftime::m_4bar_offset [private]

Also, why always 4/16 in the calculations of this value? Might be able to get rid of this member, though it's a bit tricky.

12.53.4.3 int seq64::perftime::m_tick_offset [private]

Why 16?

12.53.4.4 int seq64::perftime::m_ppqn [private]

12.53.4.5 int seq64::perftime::m_snap [private]

12.53.4.6 int seq64::perftime::m_measure_length [private]

This value is m_ppqn * 4, though eventually we want to employ a more flexible representation of measure length. Supports perftime's keystroke processing.

12.53.4.7 int seq64::perftime::m_left_marker_tick [private]

Otherwise it is -1. Supports perftime's keystroke processing.

12.53.4.8 int seq64::perftime::m_right_marker_tick [private]

Otherwise it is -1. Supports perftime's keystroke processing.

12.53.4.9 int seq64::perftime::m_perf_scale_x [private]

12.53.4.10 int seq64::perftime::m_timearea_y [private]

12.54 seq64::rc_settings Class Reference

This class contains the options formerly named "global_xxxxxx".

Public Member Functions

- rc_settings ()

  Default constructor.
- rc_settings (const rc_settings &rhs)

  Copy constructor.
- rc_settings & operator= (const rc_settings &rhs)

  Principal assignment operator.
- std::string config_filespec () const

  Constructs the full path and file specification for the "rc" file based on whether or not the legacy Seq24 filenames are being used.
- std::string user_filespec () const

  Constructs the full path and file specification for the "user" file based on whether or not the legacy Seq24 filenames are being used.
- void set_defaults ()

  Sets the default values.

- bool auto_option_save () const

  Accessor *m_auto_option_save*
- void auto_option_save (bool flag)
- bool legacy_format () const

  Accessor *m_legacy_format*
- void legacy_format (bool flag)
- bool lash_support () const

  Accessor *m_lash_support*
- void lash_support (bool flag)
- bool allow_mod4_mode () const

  Accessor *m_allow_mod4_mode*
- void allow_mod4_mode (bool flag)
- bool show_midi () const

  Accessor *m_show_midi*
- void show_midi (bool flag)
- bool priority () const

  Accessor *m_priority*
- void priority (bool flag)
- bool stats () const

  Accessor *m_stats*
- void stats (bool flag)
- bool pass_sysex () const

  Accessor *m_pass_sysex*
- void pass_sysex (bool flag)
- bool with_jack_transport () const

  Accessor *m_with_jack_transport*
- void with_jack_transport (bool flag)
- bool with_jack_master () const

  Accessor *m_with_jack_master*
- void with_jack_master (bool flag)
- bool with_jack_master_cond () const

  Accessor *m_with_jack_master_cond*
- void with_jack_master_cond (bool flag)
- bool with_jack () const

  Accessor *m_with_jack_transport m_with_jack_master, and m_with_jack_master_cond, to save client code some trouble.*
- bool jack_start_mode () const

  Accessor *m_jack_start_mode,*
- void jack_start_mode (bool flag)
- bool manual_alsa_ports () const

  Accessor *m_manual_alsa_ports*
- void manual_alsa_ports (bool flag)
- bool reveal_alsa_ports () const

  Accessor *m_reveal_alsa_ports*
- void reveal_alsa_ports (bool flag)
- bool is_pattern_playing () const

  Accessor *m_is_pattern_playing*
- void is_pattern_playing (bool flag)
- bool print_keys () const

  Accessor *m_print_keys*
- void print_keys (bool flag)
- bool device_ignore () const

Accessor *m_device_ignore*

- void device_ignore (bool flag)
- int device_ignore_num () const

  'Getter' function for member m_device_ignore_num
- interaction_method_t interaction_method () const

  'Getter' function for member m_interaction_method
- const std::string & filename () const

  'Getter' function for member m_filename
- const std::string & jack_session_uuid () const

  'Getter' function for member m_jack_session_uuid
- const std::string & last_used_dir () const

  'Getter' function for member m_last_used_dir
- const std::string & config_directory () const

  'Getter' function for member m_config_directory
- const std::string & config_filename () const

  'Getter' function for member m_config_filename
- const std::string & user_filename () const

  'Getter' function for member m_user_filename
- const std::string & config_filename_alt () const

  'Getter' function for member m_config_filename_alt;
- const std::string & user_filename_alt () const

  'Getter' function for member m_user_filename_alt
- void device_ignore_num (int value)

  'Setter' function for member m_device_ignore_num However, please note that this value, while set in the options processing of the main module, does not appear to be used anywhere in the code in seq24, Sequencer24, and this application.
- void interaction_method (interaction_method_t value)

  'Setter' function for member m_interaction_method
- void filename (const std::string &value)

  'Setter' function for member m_filename
- void jack_session_uuid (const std::string &value)

  'Setter' function for member m_jack_session_uuid
- void last_used_dir (const std::string &value)

  'Setter' function for member m_last_used_dir
- void config_directory (const std::string &value)

  'Setter' function for member m_config_directory
- void set_config_files (const std::string &value)

  'Setter' function for member m_config_filename and m_user_filename
- void config_filename (const std::string &value)

  'Setter' function for member m_config_filename ("rc")
- void user_filename (const std::string &value)

  'Setter' function for member m_user_filename ("usr")
- void config_filename_alt (const std::string &value)

  'Setter' function for member m_config_filename_alt
- void user_filename_alt (const std::string &value)

  'Setter' function for member m_user_filename_alt

Private Member Functions

- std::string home_config_directory () const

  Provides the directory for the configuration file, and also creates the directory if necessary.

Private Attributes

- bool m_auto_option_save
- bool m_legacy_format
- bool m_lash_support
- bool m_allow_mod4_mode
- bool m_show_midi
- bool m_priority
- bool m_stats
- bool m_pass_sysex
- bool m_with_jack_transport
- bool m_with_jack_master
- bool m_with_jack_master_cond
- bool m_jack_start_mode
- bool m_manual_alsa_ports
- bool m_reveal_alsa_ports
- bool m_is_pattern_playing
- bool m_print_keys
- bool m_device_ignore
- int m_device_ignore_num
- interaction_method_t m_interaction_method
- std::string m_filename

  Provides the name of current MIDI file.
- std::string m_jack_session_uuid
- std::string m_last_used_dir
- std::string m_config_directory
- std::string m_config_filename
- std::string m_user_filename
- std::string m_config_filename_alt
- std::string m_user_filename_alt

12.54.1 Constructor & Destructor Documentation

12.54.1.1 seq64::rc_settings::rc_settings ( )

12.54.1.2 seq64::rc_settings::rc_settings (const rc_settings & *rhs*)

Parameters

rhs	The source of the data for the copy.

12.54.2 Member Function Documentation

12.54.2.1 rc_settings & seq64::rc_settings::operator= (const rc_settings & *rhs*)

Parameters

rhs	The source of the data for the assignment.

Returns

Returns a reference to the destination for use in serial assignments.

12.54.2.2 std::string seq64::rc_settings::config_filespec ( ) const

Returns

If home_config_directory() returns a non-empty string, then the legacy or normal "rc" configuration file-name is appended to that result, and returned. Otherwise, an empty string is returned.

12.54.2.3 std::string seq64::rc_settings::user_filespec ( ) const

Returns

If home_config_directory() returns a non-empty string, then the legacy or normal "user" configuration file-name is appended to that result, and returned. Otherwise, an empty string is returned.

12.54.2.4 void seq64::rc_settings::set_defaults ( )

12.54.2.5 bool seq64::rc_settings::auto_option_save ( ) const [inline]

12.54.2.6 void seq64::rc_settings::auto_option_save (bool *flag*) [inline]

12.54.2.7 bool seq64::rc_settings::legacy_format ( ) const [inline]

12.54.2.8 void seq64::rc_settings::legacy_format (bool *flag*) [inline]

12.54.2.9 bool seq64::rc_settings::lash_support ( ) const [inline]

12.54.2.10 void seq64::rc_settings::lash_support (bool *flag*) [inline]

12.54.2.11 bool seq64::rc_settings::allow_mod4_mode ( ) const [inline]

12.54.2.12 void seq64::rc_settings::allow_mod4_mode (bool *flag*) [inline]

12.54.2.13 bool seq64::rc_settings::show_midi ( ) const [inline]

12.54.2.14 void seq64::rc_settings::show_midi (bool *flag*) [inline]

12.54.2.15 bool seq64::rc_settings::priority ( ) const [inline]

12.54.2.16 void seq64::rc_settings::priority (bool *flag*) [inline]

12.54.2.17 bool seq64::rc_settings::stats ( ) const [inline]

12.54.2.18 void seq64::rc_settings::stats (bool *flag*) [inline]

12.54.2.19 bool seq64::rc_settings::pass_sysex ( ) const [inline]

12.54.2.20 void seq64::rc_settings::pass_sysex (bool *flag*) [inline]

12.54.2.21 bool seq64::rc_settings::with_jack_transport ( ) const [inline]

12.54.2.22 void seq64::rc_settings::with_jack_transport (bool *flag*) [inline]

12.54.2.23 bool seq64::rc_settings::with_jack_master ( ) const [inline]

12.54.2.24 void seq64::rc_settings::with_jack_master (bool *flag*) [inline]

12.54.2.25 bool seq64::rc_settings::with_jack_master_cond ( ) const [inline]

12.54.2.26 void seq64::rc_settings::with_jack_master_cond (bool *flag*) [inline]

12.54.2.27 bool seq64::rc_settings::with_jack ( ) const [inline]

12.54.2.28 bool seq64::rc_settings::jack_start_mode ( ) const [inline]

12.54.2.29 void seq64::rc_settings::jack_start_mode (bool *flag*) [inline]

12.54.2.30 bool seq64::rc_settings::manual_alsa_ports ( ) const [inline]

12.54.2.31 void seq64::rc_settings::manual_alsa_ports (bool *flag*) [inline]

12.54.2.32 bool seq64::rc_settings::reveal_alsa_ports ( ) const [inline]

12.54.2.33 void seq64::rc_settings::reveal_alsa_ports (bool *flag*) [inline]

12.54.2.34 bool seq64::rc_settings::is_pattern_playing ( ) const [inline]

12.54.2.35 void seq64::rc_settings::is_pattern_playing (bool *flag*) [inline]

12.54.2.36 bool seq64::rc_settings::print_keys ( ) const [inline]

12.54.2.37 void seq64::rc_settings::print_keys (bool *flag*) [inline]

12.54.2.38 bool seq64::rc_settings::device_ignore ( ) const [inline]

12.54.2.39 void seq64::rc_settings::device_ignore (bool *flag*) [inline]

12.54.2.40 int seq64::rc_settings::device_ignore_num ( ) const [inline]

12.54.2.41 interaction_method_t seq64::rc_settings::interaction_method ( ) const [inline]

12.54.2.42 const std::string& seq64::rc_settings::filename ( ) const [inline]

12.54.2.43 const std::string& seq64::rc_settings::jack_session_uuid ( ) const [inline]

12.54.2.44 const std::string& seq64::rc_settings::last_used_dir ( ) const [inline]

12.54.2.45 const std::string& seq64::rc_settings::config_directory ( ) const [inline]

12.54.2.46 const std::string& seq64::rc_settings::config_filename ( ) const [inline]

12.54.2.47 const std::string& seq64::rc_settings::user_filename ( ) const [inline]

12.54.2.48 const std::string& seq64::rc_settings::config_filename_alt ( ) const [inline]

12.54.2.49 const std::string& seq64::rc_settings::user_filename_alt ( ) const [inline]

12.54.2.50 void seq64::rc_settings::device_ignore_num (int *value*)

Parameters

value	The value to use to make the setting.

12.54.2.51 void seq64::rc_settings::interaction_method (interaction_method_t *value*)

Parameters

value	The value to use to make the setting.

12.54.2.52 void seq64::rc_settings::filename (const std::string & *value*)

Parameters

value	The value to use to make the setting.

12.54.2.53 void seq64::rc_settings::jack_session_uuid (const std::string & *value*)

Parameters

value	The value to use to make the setting.

12.54.2.54 void seq64::rc_settings::last_used_dir (const std::string & *value*)

Parameters

value	The value to use to make the setting.

12.54.2.55 void seq64::rc_settings::config_directory (const std::string & *value*)

Parameters

value	The value to use to make the setting.

12.54.2.56 void seq64::rc_settings::set_config_files (const std::string & *value*)

Implements the –config option to change both configuration files ("rc" and "usr") with one option.

Parameters

value	The value to use to make the setting, if the string is not empty. If the value has an extension, it is stripped first.

12.54.2.57 void seq64::rc_settings::config_filename (const std::string & *value*)

Parameters

value	The value to use to make the setting, if the string is not empty. If there is no period in the string, then ".rc" is appended to the end of the filename.

12.54.2.58 void seq64::rc_settings::user_filename (const std::string & *value*)

Parameters

value	The value to use to make the setting, if the string is not empty. If there is no period in the string, then ".usr" is appended to the end of the filename.

12.54.2.59 void seq64::rc_settings::config_filename_alt (const std::string & *value*)

Parameters

value	The value to use to make the setting, if the string is not empty.

12.54.2.60 void seq64::rc_settings::user_filename_alt (const std::string & *value*)

Parameters

value	The value to use to make the setting.

12.54.2.61 std::string seq64::rc_settings::home_config_directory ( ) const [private]

If the legacy format is in force, then the home directory for the configuration is (in Linux) "/home/username", and the configuration file is ".seq24rc".

If the new format is in force, then the home directory is (in Linux) "/home/username/.config/sequencer64", and the configuration file is "sequencer64.rc".

Returns

Returns the selected home configuration directory. If it does not exist, or could not be created, then an empty string is returned.

12.54.3 Field Documentation

12.54.3.1 bool seq64::rc_settings::m_auto_option_save [private]

12.54.3.2 bool seq64::rc_settings::m_legacy_format [private]

12.54.3.3 bool seq64::rc_settings::m_lash_support [private]

12.54.3.4 bool seq64::rc_settings::m_allow_mod4_mode [private]

12.54.3.5 bool seq64::rc_settings::m_show_midi [private]

12.54.3.6 bool seq64::rc_settings::m_priority [private]

12.54.3.7 bool seq64::rc_settings::m_stats [private]

12.54.3.8 bool seq64::rc_settings::m_pass_sysex [private]

12.54.3.9 bool seq64::rc_settings::m_with_jack_transport [private]

12.54.3.10 bool seq64::rc_settings::m_with_jack_master [private]

12.54.3.11 bool seq64::rc_settings::m_with_jack_master_cond [private]

12.54.3.12 bool seq64::rc_settings::m_jack_start_mode [private]

12.54.3.13 bool seq64::rc_settings::m_manual_alsa_ports [private]

12.54.3.14 bool seq64::rc_settings::m_reveal_alsa_ports [private]

12.54.3.15 bool seq64::rc_settings::m_is_pattern_playing [private]

12.54.3.16 bool seq64::rc_settings::m_print_keys [private]

12.54.3.17 bool seq64::rc_settings::m_device_ignore [private]

12.54.3.18 int seq64::rc_settings::m_device_ignore_num [private]

12.54.3.19 interaction_method_t seq64::rc_settings::m_interaction_method [private]

12.54.3.20 std::string seq64::rc_settings::m_filename [private]

12.54.3.21 std::string seq64::rc_settings::m_jack_session_uuid [private]

12.54.3.22 std::string seq64::rc_settings::m_last_used_dir [private]

12.54.3.23 std::string seq64::rc_settings::m_config_directory [private]

12.54.3.24 std::string seq64::rc_settings::m_config_filename [private]

12.54.3.25 std::string seq64::rc_settings::m_user_filename [private]

12.54.3.26 std::string seq64::rc_settings::m_config_filename_alt [private]

12.54.3.27 std::string seq64::rc_settings::m_user_filename_alt [private]

12.55 seq64::rect Class Reference

A small helper class representing a rectangle.

Data Fields

- int x
  The x-coordinate of the origin of the rectangle.
- int y
  The y-coordinate of the origin of the rectangle.
- int height
  The height of the rectangle, in units of pixels.
- int width
  The width of the rectangle, in units of pixels.

12.55.1 Field Documentation

12.55.1.1 int seq64::rect::x

12.55.1.2 int seq64::rect::y

12.55.1.3 int seq64::rect::height

12.55.1.4 int seq64::rect::width

12.56 seq64::gui_drawingarea_gtk2::rect Struct Reference

A small helper structure representing a rectangle.

Data Fields

- int x
- int y
- int height
- int width

12.56.1 Field Documentation

12.56.1.1 int seq64::gui_drawingarea_gtk2::rect::x

12.56.1.2 int seq64::gui_drawingarea_gtk2::rect::y

12.56.1.3 int seq64::gui_drawingarea_gtk2::rect::height

12.56.1.4 int seq64::gui_drawingarea_gtk2::rect::width

12.57 seq64::Seq24PerfInput Class Reference

Implements the default (Seq24) performance input characteristics of this application.

Inheritance diagram for seq64::Seq24PerfInput:



Public Member Functions

- Seq24PerfInput ()
- bool on_button_press_event (GdkEventButton *a_ev, perfroll &roll)

  Handles the normal variety of button-press event.
- bool on_button_release_event (GdkEventButton *a_ev, perfroll &roll)

  Handles various button-release events.
- bool on_motion_notify_event (GdkEventMotion *a_ev, perfroll &roll)

  Handles the normal motion-notify event.

Private Member Functions

- void set_adding (bool a_adding, perfroll &roll)

  A popup menu (which one?) calls this.
- bool handle_motion_key (bool is_left, perfroll &roll)

  Handles the keystroke motion-notify event for moving a pattern back and forth in the performance.
- bool is_adding () const

  'Getter' function for member m_adding

Private Attributes

- bool m_adding

  Indicates we are in the middle of adding a sequence segment to the performance.
- midipulse m_effective_tick

  The current tick for the current segment?

Friends

- class perfroll

Additional Inherited Members

12.57.1 Constructor & Destructor Documentation

12.57.1.1 seq64::Seq24PerfInput::Seq24PerfInput ( ) [inline]

12.57.2 Member Function Documentation

12.57.2.1 bool seq64::Seq24PerfInput::on_button_press_event (GdkEventButton * *ev*, perfroll & *roll*) [virtual]

Is there any easy way to use ctrl-left-click as the middle button here?

Returns

Returns true if a modification occurred.

Implements seq64::AbstractPerfInput.

12.57.2.2 bool seq64::Seq24PerfInput::on_button_release_event (GdkEventButton * *ev,* perfroll & *roll*) [virtual]

Any use for the middle-button or ctrl-left-click we can add?

Returns

Returns true if any modification occurred.

Implements seq64::AbstractPerfInput.

12.57.2.3 bool seq64::Seq24PerfInput::on_motion_notify_event (GdkEventMotion * *ev,* perfroll & *roll*) [virtual]

Returns

Returns true if a modification occurs. This function used to always return true.

Implements seq64::AbstractPerfInput.

12.57.2.4 void seq64::Seq24PerfInput::set_adding (bool *adding,* perfroll & *roll*) [private]

What does it mean?

12.57.2.5 bool seq64::Seq24PerfInput::handle_motion_key (bool *is_left,* perfroll & *roll*) [private]

What happens when the mouse is used to drag the pattern is that, first, roll.m_drop_tick is set by left-clicking into the pattern to select it. As the pattern is dragged, the drop-tick value does not change, but the tick (converted from the moving x value) does.

Then the button-handler sets roll.m_moving = true, and calculates roll.m_drop_tick_trigger_offset = roll.m_drop_tick - p.get_sequence(dropseq)->selected_trigger_start();

The motion handler sees that roll.m_moving is true, gets the new tick value from the new x value, offsets it, and calls p.get_sequence(dropseq)->move_selected_triggers_to(tick, true).

When the user releases the left button, then roll.m_growing is turned of and the roll draw_all()'s.

Parameters

is_left	False denotes the right arrow key, and true denotes the left arrow key.
roll	Provides a reference to the parent roll, which keeps track of most of the information about the status of the window.

Returns

Returns true if there was some action able to happen that would necessitate a window update. We've updated triggers::move_selected() [called indirectly near the end of this routine] to return false if no more movement could be made. This prevents this routine from moving way ahead after movement of the selected (in the user-interface) trigger stops.

12.57.2.6 bool seq64::Seq24PerfInput::is_adding ( ) const [inline], [private]

12.57.3 Friends And Related Function Documentation

12.57.3.1 friend class perfroll [friend]

12.57.4 Field Documentation

12.57.4.1 bool seq64::Seq24PerfInput::m_adding [private]

12.57.4.2 midipulse seq64::Seq24PerfInput::m_effective_tick [private]

12.58 seq64::Seq24SeqEventInput Struct Reference

This structure implement the normal interaction methods for Seq24.

Public Member Functions

- Seq24SeqEventInput ()
  Default constructor.
- void set_adding (bool adding, seqevent &ths)
  Changes the mouse cursor to a pencil or a left pointer in the given seqevent object, depending on the first parameter.
- bool on_button_press_event (GdkEventButton *ev, seqevent &ths)
  Implements the on-button-press event callback.
- bool on_button_release_event (GdkEventButton *ev, seqevent &ths)
  Implements the on-button-release callback.
- bool on_motion_notify_event (GdkEventMotion *ev, seqevent &ths)
  Implements the on-motion-notify event.

Data Fields

- bool m_adding
  True if we're adding events via the mouse.

12.58.1 Constructor & Destructor Documentation

12.58.1.1 seq64::Seq24SeqEventInput::Seq24SeqEventInput ( ) [inline]

12.58.2 Member Function Documentation

12.58.2.1 void seq64::Seq24SeqEventInput::set_adding (bool *adding*, seqevent & *seqev*)

Modifies m_adding as well.

Parameters

adding	The value to set m_adding to, and if true, sets the mouse cursor to a pencil icon, otherwise sets it to a standard mouse-pointer icon.
seqev	The seqevent whose window will be set to "adding" mode.

12.58.2.2 bool seq64::Seq24SeqEventInput::on_button_press_event (GdkEventButton * *ev*, seqevent & *seqev*)

Set values for dragging, then reset the box that holds dirty redraw spot. Then do the rest.

Parameters

ev	The button event for the press of a mouse button.
seqev	Provides the seqevent strip to be affected by this button event.

Returns

Returns true if a likely modification was made. This function used to return true all the time.

Needs update. seqev.m_seq.unselect(); ???????

12.58.2.3 bool seq64::Seq24SeqEventInput::on_button_release_event (GdkEventButton * *ev*, seqevent & *seqev*)

Parameters

ev	The button event for the release of a mouse button.
seqev	Provides the seqevent strip to be affected by this button event.

Returns

Returns true if a likely modification was made. This function used to return true all the time.

12.58.2.4 bool seq64::Seq24SeqEventInput::on_motion_notify_event (GdkEventMotion * *ev*, seqevent & *seqev*)

Parameters

ev	The button event for the motion of the mouse cursor.
seqev	Provides the seqevent strip to be affected by this button event.

Returns

Returns true if a likely modification was made. This function used to return true all the time.

12.58.3 Field Documentation

12.58.3.1 bool seq64::Seq24SeqEventInput::m_adding

12.59 seq64::seqdata Class Reference

This class supports drawing piano-roll eventis on a window.

Inheritance diagram for seq64::seqdata:



Public Member Functions

- seqdata (sequence &seq, perform &p, int zoom, Gtk::Adjustment &hadjust)

  Principal constructor.
- virtual ~seqdata ()

  Let's provide a do-nothing virtual destructor.
- void reset ()

  This function calls update_size().
- void redraw ()

  Calls change_horz() to update the pixmap and queue up a redraw operation.
- void set_zoom (int a_zoom)

  Sets the zoom to the given value and resets the view via the reset function.
- void set_data_type (midibyte status, midibyte control)

  Sets the status to the given value, and the control to the optional given value, which defaults to 0, then calls redraw().

Private Member Functions

- int idle_redraw ()

  Draws events on this object's built-in window and pixmap.
- void update_sizes ()

  Updates the sizes in the pixmap if the view is realized, and queues up a draw operation.
- void update_pixmap ()

  Simply calls draw_events_on_pixmap().
- void draw_line_on_window ()

  Draws on vertical line on the data window.
- void xy_to_rect (int x1, int y1, int x2, int y2, int &rx, int &ry, int &rw, int &rh)

  This function takes two points, and returns an XWin rectangle, returned via the last four parameters.
- void draw_events_on (Glib::RefPtr< Gdk::Drawable > drawable)

  Draws events on the given drawable object.
- void change_horz ()

  Change the scrolling offset on the x-axis, and redraw.
- void convert_x (int x, midipulse &tick)

  This function takes screen coordinates, and gives the horizontaol tick value based on the current zoom, returned via the second parameter.
- void render_number (Glib::RefPtr< Gdk::Pixmap > &pixmap, int x, int y, const char *const num)

  Convenience function for rendering numbers.
- void draw_events_on_pixmap ()

  Simply calls draw_events_on() for this object's built-in pixmap.
- void draw_pixmap_on_window ()

  Simply queues up a draw operation.
- void on_realize ()

  Implements the on-realization event, by calling the base-class version and then allocating the resources that could not be allocated in the constructor.
- bool on_expose_event (GdkEventExpose *ev)

  Implements the on-expose event by calling draw_drawable() on the event.
- bool on_button_press_event (GdkEventButton *ev)

  Implements a mouse button-press event.
- bool on_button_release_event (GdkEventButton *ev)

  Implement a button-release event.
- bool on_motion_notify_event (GdkEventMotion *ev)

  Handles a motion-notify event.

- bool on_leave_notify_event (GdkEventCrossing *ev)

  Handles an on-leave notification event.
- bool on_scroll_event (GdkEventScroll *ev)

  Implements the on-scroll event.
- void on_size_allocate (Gtk::Allocation &)

  Handles a size-allocation event by updating m_window_x and m_window_y, and then updating all of the sizes of the data pane in update_sizes().

Private Attributes

- sequence & m_seq

  Points to the sequence whose data is being affected by this class.
- int m_zoom

  Sets the zoom value for this part of the sequence editor, one pixel == m_zoom ticks, i.e.
- int m_scroll_offset_ticks

  The value of the leftmost tick in the data pane.
- int m_scroll_offset_x

  The value of the leftmost pixel in the data pane.
- int m_number_w

  The adjusted width of a digit in a data number.
- int m_number_h

  The adjusted height of all digits in a data number.
- int m_number_offset_y

  A new value to make it easier to adapt the vertical number drawing of a data item's numeric value to a different font.
- midibyte m_status

  Holds the status byte of the next event in the sequence, and indicates What the data window is currently editing or drawing.
- midibyte m_cc

  Holds the MIDI CC byte of the next event in the sequence, and indicates What the data window is currently editing or drawing.
- Glib::RefPtr< Gdk::Pixmap > m_numbers [c_dataarea_y]

  Holds the pixmaps for each number (0 to 127) that can be drawn for a data value in the data pane.
- GdkRectangle m_old

  This rectangle is used in blanking out a data line in draw_line_on_window().
- bool m_dragging

  This value is true if the mouse is being dragged in the data pane, which is done in order to change the height and value of each data line.

Friends

- class seqroll
- class seqevent

Additional Inherited Members

12.59.1 Constructor & Destructor Documentation

12.59.1.1 seq64::seqdata::seqdata (sequence & *seq*, perform & *p*, int *zoom*, Gtk::Adjustment & *hadjust*)

In the constructor one can only allocate colors, get_window() returns 0 because this pane has not yet been realized.

Parameters

seq	The sequence that is being displayed and edited by this data pane.
p	The performance object that oversees all of the sequences. This object is needed here only to access the perform::modify() function.
zoom	The starting zoom of this pane.
hadjust	The horizontal adjustment object provided by the parent class, seqedit, that created this pane.

12.59.1.2 virtual seq64::seqdata::~seqdata ( ) [inline],[virtual]

12.59.2 Member Function Documentation

12.59.2.1 void seq64::seqdata::reset ( )

Then, regardless of whether the view is realized, updates the pixmap and queues up a draw operation.

Note

If it weren't for the is_realized() condition, we could just call update_sizes(), which does all this anyway.

12.59.2.2 void seq64::seqdata::redraw ( ) [inline]

12.59.2.3 void seq64::seqdata::set_zoom (int *z*)

Called by seqedit::set_zoom(), which validates the zoom value.

Parameters

z	The zoom value to be set.

12.59.2.4 void seq64::seqdata::set_data_type (midibyte *status*, midibyte *control*)

Perhaps we should check that at least one of the parameters causes a change.

Parameters

status	The MIDI event byte (status byte) to set.
control	The MIDI CC value to set.

12.59.2.5 int seq64::seqdata::idle_redraw ( ) [private]

This drawing is done only if there is no dragging in progress, to guarantee no flicker.

12.59.2.6 void seq64::seqdata::update_sizes ( ) [private]

It creates a pixmap with window dimensions given by m_window_x and m_window_y.

We thought there was a potential memory leak, since m_pixmap is created every time the window is resized, but valgrind says otherwise... maybe. An awful lot of Gtk leaks!

12.59.2.7 void seq64::seqdata::update_pixmap ( ) [private]

12.59.2.8 void seq64::seqdata::draw_line_on_window ( ) [private]

12.59.2.9 void seq64::seqdata::xy_to_rect (int *x1*, int *y1*, int *x2*, int *y2*, int & *rx*, int & *ry*, int & *rw*, int & *rh*) [private]

It checks the mins/maxes, then fills in x, y, and width, height.

Parameters

	x1	The input x value for the first data point.
	y1	The input y value for the first data point.
	x2	The input x value for the second data point.
	y2	The input y value for the second data point.
out	*rx*	The output for the x value of the XWin rectangle.
out	*ry*	The output for the y value of the XWin rectangle.
out	*rw*	The output for the width value of the XWin rectangle.
out	*rh*	The output for the height of the XWin rectangle.

12.59.2.10 void seq64::seqdata::draw_events_on (Glib::RefPtr< Gdk::Drawable > *drawable*) [private]

Very similar to seqevent :: draw_events_on(). And yet it doesn't handle zooming as well, must fix!

Change Note ca 2016-04-13, 2016-05-24 We now draw the data line for selected event in dark orange, instead of black.

Parameters

drawable	The given drawable object.

12.59.2.11 void seq64::seqdata::change_horz ( ) [private]

Basically identical to seqevent::change_horz().

12.59.2.12 void seq64::seqdata::convert_x (int *x*, midipulse & *tick*) [inline], [private]

12.59.2.13 void seq64::seqdata::render_number (Glib::RefPtr< Gdk::Pixmap > & *pixmap*, int *x*, int *y*, const char *const *num*) [inline], [private]

Parameters

pixmap	The reference pointer to the GDK pixmap onto which this number will be drawing.
x	The x-coordinate of the position of the text.
y	The y-coordinate of the position of the text.
num	The number to be rendered. This should be a string reference, but oh well.

12.59.2.14 void seq64::seqdata::draw_events_on_pixmap ( ) [inline], [private]

12.59.2.15 void seq64::seqdata::draw_pixmap_on_window ( ) [inline], [private]

12.59.2.16 void seq64::seqdata::on_realize ( ) [private]

It also connects up the change_horz() function.

Note that this function creates a small pixmap for every possible y-value, where y ranges from 0 to MIDI_COUNT↩ _MAX-1 = 127. It then fills each pixmap with a numeric representation of that y value, up to three digits (left-padded with spaces).

12.59.2.17 bool seq64::seqdata::on_expose_event (GdkEventExpose * *ev*) [private]

Parameters

ev	Provides the expose-event.

Returns

Always returns true.

12.59.2.18 bool seq64::seqdata::on_button_press_event (GdkEventButton * *ev*) [private]

This function pushes the undo information for the sequence, sets the drop-point, resets the box that holds dirty redraw spot, and sets m_dragging to true.

Parameters

ev	Provides the button-press event.

Returns

Always returns true.

12.59.2.19 bool seq64::seqdata::on_button_release_event (GdkEventButton * *ev*) [private]

Sets the current point. If m_dragging is true, then the sequence data is changed, the performance modification flag is set, and m_dragging is reset.

Parameters

ev	Provides the button-release event.

Returns

Returns true if a modification occurred, and in that case also sets the perform modification flag.

12.59.2.20 bool seq64::seqdata::on_motion_notify_event (GdkEventMotion * *ev*) [private]

It converts the x,y of the mouse to ticks, then sets the events in the event-data-range, updates the pixmap, draws events in the window, and draws a line on the window.

Parameters

ev	The motion event.

Returns

Returns true if a change in event data occurred. If true, then the perform modification flag is set.

12.59.2.21 bool seq64::seqdata::on_leave_notify_event (GdkEventCrossing * *ev*) [private]

Parameter "p0", the crossing point for the event, is unused.

12.59.2.22 bool seq64::seqdata::on_scroll_event (GdkEventScroll * *ev*) [private]

This scroll event only handles basic scrolling, without any modifier keys such as the Ctrl of Shift masks. If there is a note (seqroll pane) or event (seqevent pane) selected, and mouse hovers over the data area (seqdata pane), then this scrolling action will increase or decrease the value of the data item, which lengthens of shortens the line drawn.

Todo DOCUMENT the seqdata scrolling behavior in the documentation projects.

Parameters

ev	Provides the scroll-event.

Returns

Always returns true.

12.59.2.23 void seq64::seqdata::on_size_allocate (Gtk::Allocation & *r*) [private]

Parameters

r	Provides the allocation event.

12.59.3 Friends And Related Function Documentation

12.59.3.1 friend class seqroll [friend]

12.59.3.2 friend class seqevent [friend]

12.59.4 Field Documentation

12.59.4.1 sequence& seq64::seqdata::m_seq [private]

12.59.4.2 int seq64::seqdata::m_zoom [private]

the unit is ticks/pixel.

12.59.4.3 int seq64::seqdata::m_scroll_offset_ticks [private]

Adjusted in the change_horz() function.

12.59.4.4 int seq64::seqdata::m_scroll_offset_x [private]

Adjusted in the change_horz() function. It is the offset ticks divided by the zoom value, i.e. the unit is pixels..

12.59.4.5 int seq64::seqdata::m_number_w [private]

By "adjusted", well this is just a minor tweak for appearances.

12.59.4.6 int seq64::seqdata::m_number_h [private]

Basically, the character height times 3. By "adjusted", well this is just a minor tweak for appearances.

12.59.4.7 int seq64::seqdata::m_number_offset_y [private]

This value was hardwired as 8, for a character height of 10.

12.59.4.8 midibyte seq64::seqdata::m_status [private]

12.59.4.9 midibyte seq64::seqdata::m_cc [private]

12.59.4.10 Glib::RefPtr<Gdk::Pixmap> seq64::seqdata::m_numbers[c_dataarea_y] [private]

This array is filled only once, in the on_realize() function.

12.59.4.11 GdkRectangle seq64::seqdata::m_old [private]

12.59.4.12 bool seq64::seqdata::m_dragging [private]

12.60 seq64::seqedit Class Reference

Implements the Pattern Editor, which has references to:

Inheritance diagram for seq64::seqedit:



Public Member Functions

- seqedit (perform &perf, sequence &seq, int pos, int ppqn=SEQ64_USE_DEFAULT_PPQN)

  Principal constructor.
- virtual ~seqedit ()

  A rote destructor.

Private Member Functions

- void set_zoom (int zoom)

  Selects the given zoom value.
- void set_snap (int snap)

  Selects the given snap value, which is the number of ticks in a snap-sized interval.
- void set_note_length (int note_length)

  Selects the given note-length value.
- void set_beats_per_bar (int bpm)

  Set the bpm (beats per measure) value, using the given parameter, and some internal values passed to apply_length().
- void set_beat_width (int bw)

  Set the bw (beat width) value, using the given parameter, and some internal values passed to apply_length().
- void set_rec_vol (int recvol)

  Passes the given parameter to sequence::set_rec_vol().
- void horizontal_adjust (double step)

  This function provides optimization for the on_scroll_event() function.
- void vertical_adjust (double step)

  This function provides optimization for the on_scroll_event() function.
- void horizontal_set (double value)

  Sets the exact position of a horizontal scroll-bar.
- void vertical_set (double value)

  Sets the exact position of a vertical scroll-bar.
- void set_measures (int lim)

  Set the measures value, using the given parameter, and some internal values passed to apply_length().
- void apply_length (int bpm, int bw, int measures)

  Sets the sequence length based on the three given parameters.
- long get_measures ()

  Calculates the measures value based on the bpm (beats per measure), ppqn (parts per quarter note), and bw (beat width) values, and returns the resultant measures value.
- void set_midi_channel (int midichannel)

  Selects the given MIDI channel parameter in the main sequence object, so that it will use that channel.
- void set_midi_bus (int midibus)

  Selects the given MIDI buss parameter in the main sequence object, so that it will use that buss.
- void set_scale (int scale)

  Selects the given scale value.
- void set_key (int note)

  Selects the given key (signature) value.
- void set_background_sequence (int seq)

  Draws the given background sequence on the Pattern editor so that the musician has something to see that can be played against.
- void name_change_callback ()

  Set the name for the main sequence to this object's entry name.
- void play_change_callback ()

Passes the play status to the sequence object.

- void record_change_callback ()

  Passes the recording status to the sequence object.

- void q_rec_change_callback ()

  Passes the quantized-recording status to the sequence object.

- void thru_change_callback ()

  Passes the MIDI Thru status to the sequence object.

- void undo_callback ()

  Pops an undo operation from the sequence object, and then tells the segroll, seqtime, seqdata, and seqevent objects to redraw.

- void redo_callback ()

  Pops a redo operation from the sequence object, and then tell the segroll, seqtime, seqdata, and seqevent objects to redraw.

- void set_data_type (midibyte status, midibyte control=0)

  Sets the data type based on the given parameters.

- void update_all_windows ()
- void fill_top_bar ()

  This function inserts the user-interface items into the top bar or panel of the pattern editor; this bar has two rows of user interface elements.

- void create_menus ()

  Creates the various menus by pushing menu elements into the menus.

- void popup_menu (Gtk::Menu *menu)

  Pops up the given pop-up menu.

- void popup_event_menu ()

  Populates the event-selection menu that drops from the "Event" button in the bottom row of the Pattern editor.

- void popup_midibus_menu ()

  Populates the MIDI Output buss pop-up menu.

- void popup_sequence_menu ()

  Populates the "set background sequence" menu (drops from the button that has some note-bars on it at the right of the second row of the top bar).

- void popup_tool_menu ()

  Sets up the pop-up menus that are brought up by pressing the Tools button, which shows a hammer image.

- void popup_midich_menu ()

  Populates the MIDI Channel pop-up menu.

- Gtk::Image * create_menu_image (bool state=false)

  Sets the menu pixmap depending on the given state, where true is a full menu (black backgroun), and empty menu (gray background).

- bool timeout ()

  Update the window after a time out, based on dirtiness and on playback progress.

- void do_action (int action, int var)

  Implements the actions brought forth from the Tools (hammer) button.

- void mouse_action (mouse_action_e action)
- void change_focus (bool set_it=true)

  Changes what perform and mainwid see as the "current sequence".

- void handle_close ()

  Handles closing the sequence editor.

- void on_realize ()

  On realization, calls the base-class version, and connects the redraw timeout signal, timed at redraw_period_ms().

- void on_set_focus (Widget *focus)

  On receiving focus, attempt to tell mainwid that this sequence is now the current sequence.

- bool on_focus_in_event (GdkEventFocus *)

  Implements the on-focus event handling.

- bool on_focus_out_event (GdkEventFocus ∗)

  Implements the on-unfocus event handling.
- bool on_delete_event (GdkEventAny ∗event)

  Handles an on-delete event.
- bool on_scroll_event (GdkEventScroll ∗ev)

  Handles an on-scroll event.
- bool on_key_press_event (GdkEventKey ∗ev)

  Handles a key-press event.

Private Attributes

- friend seqmenu
- const int m_initial_zoom

  Provides the initial zoom, used for restoring the original zoom using the 0 key.
- int m_zoom

  Provides the zoom values: 1 2 3 4, and 1, 2, 4, 8, 16.
- int m_snap

  Used in setting the snap-to value in pulses, off = 1.
- int m_note_length

  The default length of a note to be inserted by a right-left-click operation.
- int m_scale

  Setting for the music scale, can now be saved with the sequence.
- int m_key

  Setting for the music key, can now be saved with the sequence.
- int m_bgsequence

  Setting for the background sequence, can now be saved with the sequence.
- long m_measures

  Provides the length of the sequence in measures.
- int m_ppqn

  Holds a copy of the current PPQN for the sequence (and the entire MIDI file).
- sequence & m_seq

  Holds a reference to the sequence that this window represents.
- Gtk::MenuBar ∗ m_menubar

  A number of user-interface objects for common.
- Gtk::Menu ∗ m_menu_tools

  The "hammer" tool button menu.
- Gtk::Menu ∗ m_menu_zoom

  Magnifying glass zoom menu.
- Gtk::Menu ∗ m_menu_snap

  Two-arrows grid-snap menu.
- Gtk::Menu ∗ m_menu_note_length

  Notes menu for note length.
- Gtk::Menu ∗ m_menu_length

  Pattern-length "bars" menu.
- Gtk::Menu ∗ m_menu_midich

  MIDI channel DIN menu button.
- Gtk::Menu ∗ m_menu_midibus

  MIDI output buss menu button.
- Gtk::Menu ∗ m_menu_data

  "Event" button to select data.

- Gtk::Menu * m_menu_key

  "Music key" menu button.
- Gtk::Menu * m_menu_scale

  "Music scale" menu button.
- Gtk::Menu * m_menu_sequences

  "Background sequence" button.
- Gtk::Menu * m_menu_bpm

  Beats/measure numerator menu.
- Gtk::Menu * m_menu_bw

  Beat-width denominator menu.
- Gtk::Menu * m_menu_rec_vol

  Recording level "Vol" button.
- Gtk::Adjustment * m_vadjust

  Scrollbar and adjustment objects for horizontal and vertical panning.
- Gtk::Adjustment * m_hadjust

  Horizontal motion scratchpad.
- Gtk::VScrollbar * m_vscroll_new

  Main vertical scroll-bar.
- Gtk::HScrollbar * m_hscroll_new

  Main horizontal scroll-bar.
- seqkeys * m_seqkeys_wid

  Handles the piano-keys part of the pattern-editor user-interface.
- seqtime * m_seqtime_wid

  Handles the time-line (bar or measures) part of the pattern-editor user-interface.
- seqdata * m_seqdata_wid

  Handles the event-data part of the pattern-editor user-interface.
- seqevent * m_seqevent_wid

  Handles the small event part of the pattern-editor user-interface, where events can be moved and added.
- seqroll * m_seqroll_wid

  Handles the piano-roll part of the pattern-editor user-interface.
- Gtk::Table * m_table

  More user-interface elements.
- Gtk::VBox * m_vbox

  Layout box for 3 h-boxes.
- Gtk::HBox * m_hbox

  Topmost menu/text dialog row.
- Gtk::HBox * m_hbox2

  Second row of buttons.
- Gtk::Button * m_button_undo

  Undo-edit button.
- Gtk::Button * m_button_redo

  Redo-edit button.
- Gtk::Button * m_button_quantize

  Quantize-pattern button.
- Gtk::Button * m_button_tools

  Button for the Tools menu.
- Gtk::Button * m_button_sequence

  Button for Background pattern.
- Gtk::Entry * m_entry_sequence

  Text for background pattern.
- Gtk::Button * m_button_bus

Button for MIDI Buss menu.

- Gtk::Entry * m_entry_bus

  Text showing MIDI Buss name.
- Gtk::Button * m_button_channel

  Button for the MIDI Channel.
- Gtk::Entry * m_entry_channel

  Text for the MIDI Channel.
- Gtk::Button * m_button_snap

  Button for the Grid-snap menu.
- Gtk::Entry * m_entry_snap

  Text for selected Grid-snap.
- Gtk::Button * m_button_note_length

  Button for Note-length menu.
- Gtk::Entry * m_entry_note_length

  Text showing the Note-length.
- Gtk::Button * m_button_zoom

  Button for the Zoom menu.
- Gtk::Entry * m_entry_zoom

  Text for the selected Zoom.
- Gtk::Button * m_button_length

  Button for pattern-length.
- Gtk::Entry * m_entry_length

  Text for the pattern-length.
- Gtk::Button * m_button_key

  Button for the Music Key.
- Gtk::Entry * m_entry_key

  Text for selected Music Key.
- Gtk::Button * m_button_scale

  Button for the Music Scale.
- Gtk::Entry * m_entry_scale

  Text for the Music Scale.
- Gtk::Tooltips * m_tooltips

  Tooltip collector for dialog.
- Gtk::Button * m_button_data

  Button for Event (data) menu.
- Gtk::Entry * m_entry_data

  Text for the selected Event.
- Gtk::Button * m_button_bpm

  Button for Beats/Measure menu.
- Gtk::Entry * m_entry_bpm

  Text for chosen Beats/Measure.
- Gtk::Button * m_button_bw

  Button for Beat-Width menu.
- Gtk::Entry * m_entry_bw

  Text for chosen Beat-Width.
- Gtk::Button * m_button_rec_vol

  Button for recording volume.
- Gtk::ToggleButton * m_toggle_play

  Pattern-to-MIDI record button.
- Gtk::ToggleButton * m_toggle_record

  MIDI-port-to-pattern button.

- Gtk::ToggleButton * m_toggle_q_rec

  Quantized-record MIDI button.
- Gtk::ToggleButton * m_toggle_thru

  MIDI-to-pattern-MIDI button.
- Gtk::Entry * m_entry_name

  Name of the sequence.
- midibyte m_editing_status

  Indicates what MIDI event/status the data window currently editing.
- midibyte m_editing_cc

  Indicates what MIDI CC value the data window currently editing.
- bool m_have_focus

  Indicates that the focus has already been changed to this sequence.

Static Private Attributes

- static int m_initial_snap

  Static data members.
- static int m_initial_note_length

Additional Inherited Members

12.60.1 Detailed Description

- perform
- seqroll
- seqkeys
- seqdata
- seqtime
- seqevent
- sequence

This class has a metric ton of user-interface objects and other members.

12.60.2 Constructor & Destructor Documentation

12.60.2.1 seq64::seqedit::seqedit (perform & *p*, sequence & *seq*, int *pos*, int *ppqn* = SEQ64_USE_DEFAULT_PPQN)

If provided, override the scale, key, and background-sequence with the values stored in the file with the sequence, if they are set to non-default values. This is a new feature.

Todo Offload most of the work into an initialization function like options does.

Todo Support the hightlight feature in one or both perfedit windows in the same way it is done in the mainwid.

Horizontal Gtk::Adjustment constructor: The initial value was 0 on a range from 0 to 1, with step and page increments of 1, and a page_size of 1. We can fix these values here, or create an h_adjustment() function similar to eventedit::v_adjustment(), which first gets called in on_realize().

12.60.2.2 seq64::seqedit::~seqedit ( ) [virtual]

12.60.3 Member Function Documentation

12.60.3.1 void seq64::seqedit::set_zoom (int *z*) [private]

It is passed to the seqroll, seqtime, seqdata, and seqevent objects, as well. This function doesn't check if the zoom will change, because this function might be used to initialize the zoom of the children.

The notation for zoom in the user-interface is in pixels:ticks, but I would prefer to use pulses/pixel (pulses per pixel). Oh well. Note that this value of zoom is saved to the "user" configuration file when Sequencer64 exit.

Parameters

z	The prospective zoom value to set. It is applied only if between the minimum and maximum allowed zoom values, inclusive. See the usr().min_zoom() and usr().max_zoom() function.

12.60.3.2 void seq64::seqedit::set_snap (int *s*) [private]

It is passed to the seqroll, seqevent, and sequence objects, as well.

The default initial snap is the default PPQN divided by 4, or the equivalent of a 16th note (48 ticks). The snap divisor is 192 ∗ 4 / 48 or 16.

Parameters

s	The prospective snap value to set. It is checked only to make sure it is greater than 0, to avoid a numeric exception.

12.60.3.3 void seq64::seqedit::set_note_length (int *notelength*) [private]

It is passed to the seqroll object, as well.

Warning

Currently, we don't handle changes in the global PPQN after the creation of the menu. The creation of the menu hard-wires the values of note-length. To adjust for a new global PQN, we will need to store the original PPQN (m_original_ppqn = m_ppqn), and then adjust the notelength based on the new PPQN. For example if the new PPQN is twice as high as 192, then the notelength should double, though the text displayed in the "Note length" field should remain the same. However, we do adjust for a non-default PPQN at startup time.

Parameters

notelength	Provides the note length in units of MIDI pulses.

12.60.3.4 void seq64::seqedit::set_beats_per_bar (int *bpm*) [private]

12.60.3.5 void seq64::seqedit::set_beat_width (int *bw*) [private]

12.60.3.6 void seq64::seqedit::set_rec_vol (int *recvol*) [inline], [private]

Parameters

recvol	The setting to be made, obtained from the recording-volume ("Vol") menu.

12.60.3.7 void seq64::seqedit::horizontal_adjust (double *step*) [inline], [private]

A duplicate of the one in seqroll.

Parameters

step	Provides the step value to use for adjusting the horizontal scrollbar. See gui_drawingarea_gtk2::scroll_hadjust() for more information.

12.60.3.8 void seq64::seqedit::vertical_adjust (double *step*) [inline], [private]

A near-duplicate of the one in seqroll.

Parameters

step	Provides the step value to use for adjusting the vertical scrollbar. See gui_drawingarea_gtk2::scroll_vadjust() for more information.

12.60.3.9 void seq64::seqedit::horizontal_set (double *value*) [inline], [private]

Parameters

value	The desired position. Mostly this is either 0.0 or 9999999.0 (an "infinite" value to select the start or end position.

12.60.3.10 void seq64::seqedit::vertical_set (double *value*) [inline], [private]

Parameters

value	The desired position. Mostly this is either 0.0 or 9999999.0 (an "infinite" value to select the start or end position.

12.60.3.11 void seq64::seqedit::set_measures (int *lim*) [private]

Parameters

lim	Provides the sequence length, in measures.

12.60.3.12 void seq64::seqedit::apply_length (int *bpm,* int *bw,* int *measures*) [private]

There's an implicit "adjust-triggers = true" parameter used in sequence::set_length().

Then the seqroll, seqtime, seqdata, and seqevent objects are reset().

12.60.3.13 long seq64::seqedit::get_measures ( ) [private]

Todo Create a sequence::set_units() function or a sequence::get_measures() function to forward to.

12.60.3.14 void seq64::seqedit::set_midi_channel (int *midichannel*) [private]

Should this change set the is-modified flag? Where should validation occur?

12.60.3.15 void seq64::seqedit::set_midi_bus (int *bus*) [private]

Should this change set the is-modified flag? Where should validation against the ALSA or JACK buss limits occur?

Also, it would be nice to be able to update this display of the MIDI bus in the field if we set it from the seqmenu.

12.60.3.16 void seq64::seqedit::set_scale (int *scale*) [private]

It is passed to the seqroll and seqkeys objects, as well. As a new feature, it is also passed to the sequence, so that it can be saved as part of the sequence data.

Note that the "initial value" for this parameter is a static variable that gets set to the new value, so that opening up another sequence causes the sequence to take on the new "initial value" as well. A feature, but should it be optional? Now it is, based on the setting of usr().global_seq_feature().

12.60.3.17 void seq64::seqedit::set_key (int *key*) [private]

It is passed to the seqroll and seqkeys objects, as well. As a new feature, it is also passed to the sequence, so that it can be saved as part of the sequence data.

Note that the "initial value" for this parameter is a static variable that gets set to the new value, so that opening up another sequence causes the sequence to take on the new "initial value" as well. A feature, but should it be optional? Now it is, based on the setting of usr().global_seq_feature().

12.60.3.18 void seq64::seqedit::set_background_sequence (int *seqnum*) [private]

As a new feature, it is also passed to the sequence, so that it can be saved as part of the sequence data, but only if less or equal to the maximum single-byte MIDI value, 127.

Note that the "initial value" for this parameter is a static variable that gets set to the new value, so that opening up another sequence causes the sequence to take on the new "initial value" as well. A feature, but should it be optional? Now it is, based on the setting of usr().global_seq_feature().

12.60.3.19 void seq64::seqedit::name_change_callback ( ) [private]

That name is the name the user has given to the sequence being edited.

12.60.3.20 void seq64::seqedit::play_change_callback ( ) [private]

12.60.3.21 void seq64::seqedit::record_change_callback ( ) [private]

12.60.3.22 void seq64::seqedit::q_rec_change_callback ( ) [private]

12.60.3.23 void seq64::seqedit::thru_change_callback ( ) [private]

12.60.3.24 void seq64::seqedit::undo_callback ( ) [private]

12.60.3.25 void seq64::seqedit::redo_callback ( ) [private]

12.60.3.26 void seq64::seqedit::set_data_type (midibyte *status*, midibyte *control* = 0) [private]

This function uses the hardwired array c_controller_names.

Parameters

status	The current editing status.
control	The control value. However, we really need to validate it!

12.60.3.27 void seq64::seqedit::update_all_windows ( ) [private]

12.60.3.28 void seq64::seqedit::fill_top_bar ( ) [private]

Note that, if a non-default title for the sequence is in force, then we immediately force the focus to the seqroll "widget", so that the space bar can be used to control playback, instead of immediately erasing the name of the sequence. The following commented radio-buttons were a visual way to select the modes of note editing (select, draw, and grow). These can easily be done with the left mouse button, keystrokes, or some other tricks, though.

12.60.3.29 void seq64::seqedit::create_menus ( ) [private]

The first menu is the Zoom menu, represented in the pattern/sequence editor by a button with a magnifying glass. The values are "pixels to ticks", where "ticks" are actually the "pulses" of "pulses per quarter note". We would prefer the notation "n" instead of "1:n", as in "n pulses per pixel".

Note that many of the setups here could be loops through data structures. The Snap menu is actually the Grid Snap button, which shows two arrows pointing to a central bar. This menu somewhat duplicates the same menu in perfedit.

This menu lets one set the key of the sequence, and is brought up by the button with the "golden key" image on it.

This button shows a down around for the bottom half of the time signature. It's tooltip is "Time signature. Length of beat." But it is called bw, or beat width, in the code.

This menu is shown when pressing the button at the bottom of the window that has "Vol" as its label. Let's show the numbers as well to help the user. And we'll have to document this change.

This menu sets the scale to show on the panel, and the button shows a "staircase" image. See the c_music_scales enumeration defined in the globals module.

This section sets up two different menus. The first is m_menu_length. This menu lets one set the sequence length in bars. The second menu is the m_menu_bpm, or BPM, which here means "beats per measure" (not "beats per minute").

12.60.3.30 void seq64::seqedit::popup_menu (Gtk::Menu * *menu*) [private]

12.60.3.31 void seq64::seqedit::popup_event_menu ( ) [private]

This menu has a large number of items. I think they are filled in in code, but can also be loaded from ~/.seq24usr. To be determined. Create the 8 sub-menus for the various ranges of controller changes, shown 16 per sub-menu.

12.60.3.32 void seq64::seqedit::popup_midibus_menu ( ) [private]

The MIDI busses are obtained by getting the mastermidibus object, and iterating through the busses that it contains.

12.60.3.33 void seq64::seqedit::popup_sequence_menu ( ) [private]

It is populated with an "Off" menu entry, and a second "[0]" menu entry that pulls up a drop-down menu of all of the patterns/sequences that are present in the MIDI file for screen-set 0. If more screensets have active sequences, then their screen-set number appears in the screen-set section of the menu.

Now, at present, we can only save background sequence numbers that are less than 128, which means the sequences from 0 to 127, or the first four screen sets. Higher sequences can be selected, but, right now, they cannot be saved. We'll probably fix that at some point, low priority.

12.60.3.34 void seq64::seqedit::popup_tool_menu ( ) [private]

This button shows three sub-menus that need to be filled in by this function. All the functions accessed here seem to be implemented by the do_action() function.

12.60.3.35 void seq64::seqedit::popup_midich_menu ( ) [private]

12.60.3.36 Gtk::Image * seq64::seqedit::create_menu_image (bool *state* = false) [private]

12.60.3.37 bool seq64::seqedit::timeout ( ) [private]

Note the new call to seqroll::follow_progress(). This allows the seqroll to pop to the next frame of events to continue to show the moving progress bar. Does this need to be an option? It only affects patterns longer than a measure or two, whatever the width of the seqroll window is. This is a new feature that is not in seq24.

What about seqtime? That doesn't change.

12.60.3.38 void seq64::seqedit::do_action (int *action,* int *var*) [private]

Note that the push_undo() calls push all of the current events (in sequence::m_events) onto the stack (as a single entry).

12.60.3.39 void seq64::seqedit::mouse_action (mouse_action_e *action*) [private]

12.60.3.40 void seq64::seqedit::change_focus (bool *set_it* = true) [private]

Similar to the same function in eventedit.

Parameters

set_it	If true (the default value), indicates we want focus, otherwise we want to give up focus.

12.60.3.41 void seq64::seqedit::handle_close ( ) [private]

12.60.3.42 void seq64::seqedit::on_realize ( ) [private]

12.60.3.43 void seq64::seqedit::on_set_focus (Widget * *focus*) [private]

Only works in certain circumstances.

12.60.3.44 bool seq64::seqedit::on_focus_in_event (GdkEventFocus *) [private]

12.60.3.45 bool seq64::seqedit::on_focus_out_event (GdkEventFocus *) [private]

12.60.3.46 bool seq64::seqedit::on_delete_event (GdkEventAny * *event*) [private]

It tells the sequence to stop recording, tells the perform object's mastermidibus to stop processing input, and sets the sequence object's editing flag to false.

Warning

This function also calls "delete this"!

Returns

Always returns false.

12.60.3.47 bool seq64::seqedit::on_scroll_event (GdkEventScroll * *ev*) [private]

This handles moving the scroll wheel on a mouse or do a two-fingered scrolling action on a touchpad. If no modifier key is pressed, this moves the view up or down on the "notes" coordinate, showing different piano keys. This behavior is implemented in seqkeys::on_scroll_event(), and is called into play by returning false here.

If the Ctrl key is pressed, then the scrolling action causes the view to zoom in or out. This behavior is implemented here.

If the Shift key is pressed, then the scrolling action moves the view horizontally on the time-line (measures-line) of the piano roll. This behavior is implemented here.

12.60.3.48 bool seq64::seqedit::on_key_press_event (GdkEventKey * *ev*) [private]

A number of new keystrokes are processed, so that we can lessen the reliance on the mouse and work a little faster.

```
-   Ctrl-W keypress.  This keypress closes the sequence/pattern editor
    window by way of calling on_delete_event().  We could apply this
    convention to all the other windows.
-   z 0 Z zoom keys.  "z" zooms out, "Z" (Shift-z) zooms in, and "0"
    resets the zoom to the default.
-   Page-Up and Page-Down.  Moves up and down in the piano roll.
-   Home and End.  Page to the top or the bottom of the piano roll.
-   Shift-Page-Up and Shift-Page-Down.  Move left and right in the
    piano roll.
-   Shift-Home and Shift-End.  Page to the start or the end of the
    piano roll.
-   Ctrl-Page-Up and Ctrl-Page-Down.  Mirrors the zoom-in and zoom-out
    capabilities of scrolling up and down with the mouse while the
    Ctrl key is pressed.
```

The Keypad-End key is an issue on our ASUS "gaming" laptop. Whether it is seen as a "1" or an "End" key depends on an interaction between the Shift and the Num Lock key. Annoying, takes some time to get used to.

Parameters

ev	Provides the keystroke event to be handled.

Returns

Returns true if we handled the keystroke here. Otherwise, returns the value of Gtk::Window::on_key_press↩ _event(ev).

12.60.4 Field Documentation

12.60.4.1 friend seq64::seqedit::seqmenu [private]

12.60.4.2 int seq64::seqedit::m_initial_snap [static], [private]

These items apply to all of the instances of seqedit, and are passed on to the following constructors:

- seqdata

- seqevent
- seqroll
- seqtime

The snap and note-length defaults would be good to write to the "user" configuration file. The scale and key would be nice to write to the proprietary section of the MIDI song. Or, even more flexibly, to each sequence, if that makes sense to do, since all tracks would generally be in the same key. Right, Charles Ives?

Note that, currently, that some of these "initial values" are modified, so that they are "contagious". That is, the next sequence to be opened in the sequence editor will adopt these values. This is a long-standing feature of Seq24, but strikes us as a bit surprising.

Change Note ca 2016-04-10 If we just double the PPQN, then the snap divisor becomes 32, and the snap interval is a 32nd note. We would like to keep it at a 16th note. We correct the snap ticks to the actual PPQN ratio.

12.60.4.3 int seq64::seqedit::m_initial_note_length [static], [private]

12.60.4.4 const int seq64::seqedit::m_initial_zoom [private]

12.60.4.5 int seq64::seqedit::m_zoom [private]

The value of zoom is the same as the number of pixels per tick on the piano roll.

12.60.4.6 int seq64::seqedit::m_snap [private]

12.60.4.7 int seq64::seqedit::m_note_length [private]

12.60.4.8 int seq64::seqedit::m_scale [private]

12.60.4.9 int seq64::seqedit::m_key [private]

12.60.4.10 int seq64::seqedit::m_bgsequence [private]

12.60.4.11 long seq64::seqedit::m_measures [private]

12.60.4.12 int seq64::seqedit::m_ppqn [private]

12.60.4.13 sequence& seq64::seqedit::m_seq [private]

12.60.4.14 Gtk::MenuBar* seq64::seqedit::m_menubar [private]

Many of these are menu items, and are associated with buttons that, when pressed, bring up the menu for display and selection of its entries.The top bar with menu buttons.

12.60.4.15 Gtk::Menu* seq64::seqedit::m_menu_tools [private]

12.60.4.16 Gtk::Menu* seq64::seqedit::m_menu_zoom [private]

12.60.4.17 Gtk::Menu* seq64::seqedit::m_menu_snap [private]

12.60.4.18 Gtk::Menu* seq64::seqedit::m_menu_note_length [private]

12.60.4.19 Gtk::Menu* seq64::seqedit::m_menu_length [private]

12.60.4.20 Gtk::Menu* seq64::seqedit::m_menu_midich [private]

12.60.4.21 Gtk::Menu* seq64::seqedit::m_menu_midibus [private]

12.60.4.22 Gtk::Menu* seq64::seqedit::m_menu_data [private]

12.60.4.23 Gtk::Menu* seq64::seqedit::m_menu_key [private]

12.60.4.24 Gtk::Menu* seq64::seqedit::m_menu_scale [private]

12.60.4.25 Gtk::Menu* seq64::seqedit::m_menu_sequences [private]

12.60.4.26 Gtk::Menu* seq64::seqedit::m_menu_bpm [private]

12.60.4.27 Gtk::Menu* seq64::seqedit::m_menu_bw [private]

12.60.4.28 Gtk::Menu* seq64::seqedit::m_menu_rec_vol [private]

12.60.4.29 Gtk::Adjustment* seq64::seqedit::m_vadjust [private]

Vertical position descriptor.

12.60.4.30 Gtk::Adjustment* seq64::seqedit::m_hadjust [private]

12.60.4.31 Gtk::VScrollbar* seq64::seqedit::m_vscroll_new [private]

12.60.4.32 Gtk::HScrollbar* seq64::seqedit::m_hscroll_new [private]

12.60.4.33 seqkeys* seq64::seqedit::m_seqkeys_wid [private]

This item draws the piano-keys at the left of the seqedit window.

12.60.4.34 seqtime* seq64::seqedit::m_seqtime_wid [private]

This is the location where the measure numbers and the END marker are shown.

12.60.4.35 seqdata* seq64::seqedit::m_seqdata_wid [private]

This is the area at the bottom of the window that shows value lines for the selected kinds of events.

12.60.4.36 seqevent* seq64::seqedit::m_seqevent_wid [private]

12.60.4.37 seqroll* seq64::seqedit::m_seqroll_wid [private]

12.60.4.38 Gtk::Table* seq64::seqedit::m_table [private]

These items provide a number of buttons and text-entry fields, as well as their layout.The layout table for editor.

12.60.4.39 Gtk::VBox* seq64::seqedit::m_vbox [private]

12.60.4.40 Gtk::HBox* seq64::seqedit::m_hbox [private]

12.60.4.41 Gtk::HBox* seq64::seqedit::m_hbox2 [private]

12.60.4.42 Gtk::Button* seq64::seqedit::m_button_undo [private]

12.60.4.43 Gtk::Button* seq64::seqedit::m_button_redo [private]

12.60.4.44 Gtk::Button* seq64::seqedit::m_button_quantize [private]

12.60.4.45 Gtk::Button* seq64::seqedit::m_button_tools [private]

12.60.4.46 Gtk::Button* seq64::seqedit::m_button_sequence [private]

12.60.4.47 Gtk::Entry* seq64::seqedit::m_entry_sequence [private]

12.60.4.48 Gtk::Button* seq64::seqedit::m_button_bus [private]

12.60.4.49 Gtk::Entry* seq64::seqedit::m_entry_bus [private]

12.60.4.50 Gtk::Button* seq64::seqedit::m_button_channel [private]

12.60.4.51 Gtk::Entry* seq64::seqedit::m_entry_channel [private]

12.60.4.52 Gtk::Button* seq64::seqedit::m_button_snap [private]

12.60.4.53 Gtk::Entry* seq64::seqedit::m_entry_snap [private]

12.60.4.54 Gtk::Button* seq64::seqedit::m_button_note_length [private]

12.60.4.55 **Gtk::Entry* seq64::seqedit::m_entry_note_length** [private]

12.60.4.56 **Gtk::Button* seq64::seqedit::m_button_zoom** [private]

12.60.4.57 **Gtk::Entry* seq64::seqedit::m_entry_zoom** [private]

12.60.4.58 **Gtk::Button* seq64::seqedit::m_button_length** [private]

12.60.4.59 **Gtk::Entry* seq64::seqedit::m_entry_length** [private]

12.60.4.60 **Gtk::Button* seq64::seqedit::m_button_key** [private]

12.60.4.61 **Gtk::Entry* seq64::seqedit::m_entry_key** [private]

12.60.4.62 **Gtk::Button* seq64::seqedit::m_button_scale** [private]

12.60.4.63 **Gtk::Entry* seq64::seqedit::m_entry_scale** [private]

12.60.4.64 **Gtk::Tooltips* seq64::seqedit::m_tooltips** [private]

12.60.4.65 **Gtk::Button* seq64::seqedit::m_button_data** [private]

12.60.4.66 **Gtk::Entry* seq64::seqedit::m_entry_data** [private]

12.60.4.67 **Gtk::Button* seq64::seqedit::m_button_bpm** [private]

12.60.4.68 **Gtk::Entry* seq64::seqedit::m_entry_bpm** [private]

12.60.4.69 **Gtk::Button* seq64::seqedit::m_button_bw** [private]

12.60.4.70 **Gtk::Entry* seq64::seqedit::m_entry_bw** [private]

12.60.4.71 **Gtk::Button* seq64::seqedit::m_button_rec_vol** [private]

12.60.4.72 **Gtk::ToggleButton* seq64::seqedit::m_toggle_play** [private]

12.60.4.73 **Gtk::ToggleButton* seq64::seqedit::m_toggle_record** [private]

12.60.4.74 **Gtk::ToggleButton* seq64::seqedit::m_toggle_q_rec** [private]

12.60.4.75 **Gtk::ToggleButton* seq64::seqedit::m_toggle_thru** [private]

12.60.4.76 **Gtk::Entry* seq64::seqedit::m_entry_name** [private]

12.60.4.77 **midibyte seq64::seqedit::m_editing_status** [private]

12.60.4.78 midibyte seq64::seqedit::m_editing_cc [private]

12.60.4.79 bool seq64::seqedit::m_have_focus [private]

12.61 seq64::seqevent Class Reference

Implements the piano event drawing area.

Inheritance diagram for seq64::seqevent:



Public Member Functions

- seqevent (perform &p, sequence &seq, int zoom, int snap, seqdata &seqdata_wid, Gtk::Adjustment &hadjust, int ppqn=SEQ64_USE_DEFAULT_PPQN)

  Principal constructor.
- virtual ~seqevent ()

  Let's provide a do-nothing virtual destructor.
- void reset ()

  This function basically resets the whole widget as if it was realized again.
- void redraw ()

  Adjusts the scrolling offset for ticks, updates the pixmap, and draws it on the window.
- void set_zoom (int zoom)

  Sets zoom to the given value, and resets if the value ended up being changed.
- void set_snap (int snap)

  'Setter' function for member m_snap Simply sets the snap member.
- void set_data_type (midibyte status, midibyte control)

  Sets the status to the given parameter, and the CC value to the given optional control parameter, which defaults to 0.
- void update_sizes ()

  If the window is realized, this function creates a pixmap with window dimensions, the updates the pixmap, and queues up a redraw.
- void draw_background ()

  This function updates the background.
- void draw_events_on_pixmap ()

  This function fills the main pixmap with events.
- void draw_pixmap_on_window ()

  This function currently just queues up a draw operation for the pixmap.
- void draw_selection_on_window ()

  Draw the selected events on the window.
- void update_pixmap ()

  Redraws the background pixmap on the main pixmap, then puts the events on.

Private Member Functions

- virtual void force_draw ()

  Forces a draw on the current drawable area of the window.
- int idle_redraw ()

  Implements redraw while idling.
- void x_to_w (int x1, int x2, int &x, int &w)

  This function checks the mins / maxes.
- void drop_event (midipulse tick)

  Drops (adds) an event at the given tick.
- void draw_events_on (Glib::RefPtr< Gdk::Drawable > draw)

  Draws events on the given drawable object.
- void start_paste ()

  Starts a paste operation.
- void change_horz ()

  Changes the horizontal scrolling offset for ticks, then updates the pixmap and forces a redraw.
- void convert_x (int x, midipulse &tick)

  Takes the screen x coordinate, multiplies it by the current zoom, and returns the tick value in the given parameter.
- void convert_t (midipulse tick, int &x)

Converts the given tick value to an x corrdinate, based on the zoom, and returns it via the second parameter.

- void snap_y (int &y)

  This function performs a 'snap' on y.
- void snap_x (int &x)

  This function performs a 'snap' on x.
- void on_realize ()

  Implements the on-realize callback.
- bool on_expose_event (GdkEventExpose *ev)

  Implements the on-expose event callback.
- bool on_button_press_event (GdkEventButton *ev)

  Implements the on-button-press event callback.
- bool on_button_release_event (GdkEventButton *ev)

  Implements the on-button-release event callback.
- bool on_motion_notify_event (GdkEventMotion *ev)

  Implements the on-motion-notify event callback.
- bool on_focus_in_event (GdkEventFocus *)

  Responds to a focus event by setting the HAS_FOCUS flag.
- bool on_focus_out_event (GdkEventFocus *)

  Responds to a unfocus event by resetting the HAS_FOCUS flag.
- bool on_key_press_event (GdkEventKey *p0)

  Implements the key-press event callback function.
- void on_size_allocate (Gtk::Allocation &)

  Implements the on-size-allocate event callback.

Private Attributes

- FruitySeqEventInput m_fruity_interaction

  Provides the mouse-handling paradigm for the fruity interaction.
- Seq24SeqEventInput m_seq24_interaction

  Provides the normal mouse-handling for Sequencer64.
- sequence & m_seq

  Provides a reference to the sequence whose data is represented in this seqevent object.
- int m_zoom

  Zoom setting, means that one pixel == m_zoom ticks.
- int m_snap

  The grid-snap setting for the event bar grid.
- int m_ppqn

  The value to use for the PPQN for this sequence.
- GdkRectangle m_old

  Used in drawing the event selection in the thing event row.
- GdkRectangle m_selected

  Used in moving and pasting the selected events in the thin event row.
- int m_scroll_offset_ticks

  Provides the offset of the ticks in the event view based on where the scroll-bar has moved the view "window".
- int m_scroll_offset_x

  Provides the offset of the pixels in the event view based on where the scroll-bar has moved the view "window".
- seqdata & m_seqdata_wid

  The data view that parallels this event view.
- bool m_selecting

  Used when highlighting a bunch of events.

- bool m_moving_init

  Used externally by the fruityseq and seq24seq modules, to initialize the act of moving events.
- bool m_moving

  Indicates that this pane is in the act of moving a selection.
- bool m_growing

  Used externally by the fruityseq and seq24seq modules, when growing the event duration.
- bool m_painting

  Used externally by the fruityseq and seq24seq modules, in painting the selected events.
- bool m_paste

  Indicates that we've selected some events and are in paste mode.
- int m_move_snap_offset_x

  Used externally by the fruityseq and seq24seq modules, in snapping.
- midibyte m_status

  Indicates what is the data window currently editing.
- midibyte m_cc

  Indicates what is the data window currently editing.

Friends

- struct FruitySeqEventInput
- struct Seq24SeqEventInput

Additional Inherited Members

12.61.1 Constructor & Destructor Documentation

12.61.1.1 seq64::seqevent::seqevent (perform & *p*, sequence & *seq*, int *zoom*, int *snap*, seqdata & *seqdata_wid*, Gtk::Adjustment & *hadjust*, int *ppqn* = SEQ64_USE_DEFAULT_PPQN)

Parameters

p	The "parent" perform object controlling all of the sequences.
seq	The current sequence operated on by this object.
zoom	The initial zoom value.
snap	The initial snap value.
seqdata_wid	The data pane that this event pane is associated with.
hadjust	The horizontal scroll-bar.
ppqn	The initial PPQN value.

12.61.1.2 virtual seq64::seqevent::~seqevent ( ) [inline], [virtual]

12.61.2 Member Function Documentation

12.61.2.1 void seq64::seqevent::reset ( )

Basically identical to seqtime::reset().

12.61.2.2 void seq64::seqevent::redraw ( )

Somewhat similar to seqroll::redraw().

12.61.2.3 void seq64::seqevent::set_zoom (int *z*)

Parameters

z	The desired zoom value, presumably already validated by the caller.

12.61.2.4 void seq64::seqevent::set_snap (int *snap*) [inline]

The parameter is not validated.

12.61.2.5 void seq64::seqevent::set_data_type (midibyte *status*, midibyte *control*)

Then redraws.

Parameters

status	The status/event byte to set. For example, EVENT_NOTE_ON and EVENT_NOTE off. This byte should have the channel nybble cleared.
control	The MIDI CC byte to set.

12.61.2.6 void seq64::seqevent::update_sizes ( )

This ends up filling the background with dotted lines, etc.

12.61.2.7 void seq64::seqevent::draw_background ( )

It sets the foreground to white, draws the rectangle, in order to clear the pixmap. The build-time option SEQ64↩ _SOLID_PIANOROLL_GRID causes solid lines to be drawn, in gray, instead of dotted black lines, for a smoother look.

Also, as a trial option, if the current data type is EVENT_NOTE_ON, EVENT_NOTE_OFF, and EVENT_AFTER↩ TOUCH, we draw the background in light grey to remind the user that there are issues in copying or moving these events around (unlinked) by themselves.

12.61.2.8 void seq64::seqevent::draw_events_on_pixmap ( )

12.61.2.9 void seq64::seqevent::draw_pixmap_on_window ( )

Old comments:

```
It then tells event to do the same.  We changed something on this
window, and chances are we need to update the event widget as well and
update our velocity window.
```

12.61.2.10 void seq64::seqevent::draw_selection_on_window ( )

12.61.2.11 void seq64::seqevent::update_pixmap ( )

12.61.2.12 void seq64::seqevent::force_draw ( ) [private], [virtual]

Reimplemented from seq64::gui_drawingarea_gtk2.

12.61.2.13 int seq64::seqevent::idle_redraw ( ) [private]

Who calls this routine? Probably the default timer routine, but not sure.

Returns

Always returns true.

12.61.2.14 void seq64::seqevent::x_to_w (int *x1*, int *x2*, int & *x*, int & *w*) [private]

Then it fills in x and the width.

Parameters

	x1	The "left" x value.
	x2	The "right" x value.
out	*x*	The destination for the converted x value.
out	*w*	The destination for the converted width value.

12.61.2.15 void seq64::seqevent::drop_event (midipulse *tick*) [private]

It sets the first byte properly for after-touch, program-change, channel-pressure, and pitch-wheel. The type of event is determined by m_status.

Parameters

tick	The destination time (division, pulse, tick) for the event to be dropped at.

12.61.2.16 void seq64::seqevent::draw_events_on (Glib::RefPtr< Gdk::Drawable > *drawable*) [private]

Very similar to seqdata::draw_events_on().

Parameters

drawable	The given drawable object.

12.61.2.17 void seq64::seqevent::start_paste ( ) [private]

It gets the clipboard box that selected elements are in, makes a coordinate conversion, and then, sets the m_↩ selected rectangle to hold the (x,y,w,h) of the selected events.

12.61.2.18 void seq64::seqevent::change_horz ( ) [private]

Very similar to seqroll::change_horz(). Basically identical to seqdata::change_horz().

12.61.2.19 void seq64::seqevent::convert_x (int *x,* midipulse & *tick*) [inline], [private]

Why not just return it normally?

Parameters

	x	The x (pixel) value to convert.
out	*tick*	The destination for the converted x value.

12.61.2.20 void seq64::seqevent::convert_t (midipulse *tick,* int & *x*) [inline], [private]

Why not just return it normally?

Parameters

	tick	The tick (pulse) value to convert.
out	*x*	The destination for the converted tick value.

12.61.2.21 void seq64::seqevent::snap_y (int & *y*) [inline], [private]

Parameters

out	*y*	The return parameter for the conversion. Why not just return the value?

12.61.2.22 void seq64::seqevent::snap_x (int & *x*) [private]

- snap = number pulses to snap to
- m_zoom = number of pulses per pixel
- Therefore snap / m_zoom = number of pixels to snap to.

Parameters

out	*x*	The output destination for the snapped x value.

12.61.2.23 void seq64::seqevent::on_realize ( ) [private]

It calls the base-class version, and then allocates additional resource not allocated in the constructor. Finally, it connects up the change_horz function.

12.61.2.24 bool seq64::seqevent::on_expose_event (GdkEventExpose * *ev*) [private]

Parameters

ev	The expose event.

12.61.2.25 bool seq64::seqevent::on_button_press_event (GdkEventButton * *ev*) [private]

It distinguishes between the Seq24 and Fruity varieties of mouse interaction.

Odd. In the legacy code, each case fell through to the next case to the "default" case! We will assume for now that this is incorrect.

Note that returning "true" from a Gtkmm event-handler stops the propagation of the event to higher-level widgets. The Fruity and Seq24 event handlers return true, always. In the legacy code, though, the fall-through code caused false to be returned, always. Not sure what effect this had. Added some fixes, but then commented them out until better testing can be done.

Parameters

ev	The button event.

Returns

Returns true if the button-press was handled.

12.61.2.26 bool seq64::seqevent::on_button_release_event (GdkEventButton * *ev*) [private]

It distinguishes between the Seq24 and Fruity varieties of mouse interaction.

Odd. The fruity case fell through to the Seq24 case. We will assume for now that this is correct. Added some fixes, but then commented them out until better testing can be done.

Parameters

ev	The button event.

Returns

Returns true if the button-press was handled.

12.61.2.27 bool seq64::seqevent::on_motion_notify_event (GdkEventMotion * *ev*) [private]

It distinguishes between the Seq24 and Fruity varieties of mouse interaction.

Odd. The fruity case fell through to the Seq24 case. We will assume for now that this is correct. Added some fixes, but then commented them out until better testing can be done.

Parameters

ev	The motion event.

Returns

Returns true if the motion-event was handled.

12.61.2.28 bool seq64::seqevent::on_focus_in_event (GdkEventFocus *) [private]

Parameter "ev" is the focus event, unused.

Returns

Always returns false.

12.61.2.29 bool seq64::seqevent::on_focus_out_event (GdkEventFocus *) [private]

Parameter "ev" is the focus event, unused.

Returns

Always returns false.

12.61.2.30 bool seq64::seqevent::on_key_press_event (GdkEventKey * *ev*) [private]

It handles deleted a selection via the Backspace or Delete keys, cut via Ctrl-X, copy via Ctrl-C, paste via Ctrl-V, and undo via Ctrl-Z.

Would be nice to provide redo functionality via Ctrl-Y. :-)

Parameters

ev	The key-press event.

Returns

Returns true if an event was handled. Only some of the handled events also cause the perform modification flag to be set as a side-effect.

12.61.2.31 void seq64::seqevent::on_size_allocate (Gtk::Allocation & *a*) [private]

The m_window_x and m_window_y values are set to the allocation width and height, respectively.

Parameters

a	The allocation to be processed.

12.61.3 Friends And Related Function Documentation

12.61.3.1 friend struct FruitySeqEventInput [friend]

12.61.3.2 friend struct Seq24SeqEventInput [friend]

12.61.4 Field Documentation

12.61.4.1 FruitySeqEventInput seq64::seqevent::m_fruity_interaction [private]

Why should we need both at the same time? Just load the one that is specified in the configuration.

12.61.4.2 Seq24SeqEventInput seq64::seqevent::m_seq24_interaction [private]

12.61.4.3 sequence& seq64::seqevent::m_seq [private]

12.61.4.4 int seq64::seqevent::m_zoom [private]

12.61.4.5 int seq64::seqevent::m_snap [private]

Same meaning as for the piano roll. This value is the denominator of the note size used for the snap.

12.61.4.6 int seq64::seqevent::m_ppqn [private]

Used in snap and zoom scaling.

12.61.4.7 GdkRectangle seq64::seqevent::m_old [private]

12.61.4.8 GdkRectangle seq64::seqevent::m_selected [private]

12.61.4.9 int seq64::seqevent::m_scroll_offset_ticks [private]

12.61.4.10 int seq64::seqevent::m_scroll_offset_x [private]

Set to m_scroll_offset_ticks divided by m_zoom.

12.61.4.11 seqdata& seq64::seqevent::m_seqdata_wid [private]

12.61.4.12 bool seq64::seqevent::m_selecting [private]

12.61.4.13 bool seq64::seqevent::m_moving_init [private]

12.61.4.14 bool seq64::seqevent::m_moving [private]

WARNING: This operation seems to have a bug. It makes the events very very long. This bug exists in Seq24.

12.61.4.15 bool seq64::seqevent::m_growing [private]

Does growing work in this view? Need to do some better testing.

12.61.4.16 bool seq64::seqevent::m_painting [private]

12.61.4.17 bool seq64::seqevent::m_paste [private]

12.61.4.18 int seq64::seqevent::m_move_snap_offset_x [private]

12.61.4.19 midibyte seq64::seqevent::m_status [private]

The current status/event byte.

12.61.4.20 midibyte seq64::seqevent::m_cc [private]

The current MIDI CC value.

12.62 seq64::seqkeys Class Reference

This class implements the left side piano of the pattern/sequence editor.

Inheritance diagram for seq64::seqkeys:



Public Member Functions

- seqkeys (sequence &seq, perform &p, Gtk::Adjustment &vadjust)

  Principal constructor.
- virtual ~seqkeys ()

  Let's provide a do-nothing virtual destructor.
- void set_scale (int scale)

Sets the musical scale, then resets.

- void set_key (int key)

  Sets the musical key, then resets.

- void set_hint_key (int key)

  Sets a key to grey so that it can serve as a scale hint.

- void set_hint_state (bool state)

  Sets the hint state to the given value.

Private Member Functions

- virtual void force_draw ()

  Forces a draw operation on the whole window.

- void draw_area ()

  Draws the updated pixmap on the drawable area of the window where the keys' location is hardwired.

- void update_pixmap ()

  Updates the pixmaps to prepare it for the next draw operation.

- void convert_y (int y, int &note)

  Takes the screen y coordinate, and returns the note value in the second parameter.

- void draw_key (int key, bool state)

  Draws the given key according to the given state.

- void change_vert ()

  Changes the y offset of the scrolling, and the forces a draw.

- void update_sizes ()
- void reset ()

  Resetting the keys view updates the pixmap and queues up a draw operation.

- bool is_black_key (int key) const

  Detects a black key.

- void on_realize ()

  Implements the on-realize event.

- bool on_expose_event (GdkEventExpose ∗ev)

  Implements the on-expose event, by drawing on the window.

- bool on_button_press_event (GdkEventButton ∗ev)

  Implements the on-button-press event callback.

- bool on_button_release_event (GdkEventButton ∗ev)

  Implements the on-button-release event callback.

- bool on_motion_notify_event (GdkEventMotion ∗p0)

  Implements the on-motion-notify event handler.

- bool on_enter_notify_event (GdkEventCrossing ∗p0)

  Implements the on-enter notification event handler.

- bool on_leave_notify_event (GdkEventCrossing ∗p0)

  Implements the on-leave notification event handler.

- bool on_scroll_event (GdkEventScroll ∗ev)

  Implements the on-scroll-event notification event handler.

- void on_size_allocate (Gtk::Allocation &)

  Implements the on-size-allocation notification event handler.

Private Attributes

- sequence & m_seq

  The sequence object that the keys pane will be using.
- int m_scroll_offset_key

  Provides the value of the current top key in the keys pane.
- int m_scroll_offset_y

  Provides the value of the current top key in the keys pane in units of relative pixels.
- bool m_hint_state

  Indicates if a piano key is set to indicate where on the pitch scale the mouse cursor is sitting.
- int m_hint_key

  Indicates the current y-value of the mouse pointer in units of key value.
- bool m_keying

  Set to true while the left mouse button is being pressed.
- int m_keying_note

  The note to be played when selected in the seqkeys pane.
- int m_scale

  This member holds the scale value for the musical scale for the current edit of the sequence.
- int m_key

  This member holds the key value for the musical key for the current edit of the sequence.
- bool m_show_octave_letters

  The default value is to show the octave letters on the vertical virtual keyboard.

Additional Inherited Members

12.62.1 Constructor & Destructor Documentation

12.62.1.1 seq64::seqkeys::seqkeys (sequence & *seq*, perform & *p*, Gtk::Adjustment & *vadjust*)

Parameters

seq	Provides the sequence object to which this seqkeys pane is associated.
p	Provides the performance object to which this seqkeys pane (and all sequences) are associated.
vadjust	The range object for the vertical scrollbar linked to the position in the seqkeys pane.

12.62.1.2 virtual seq64::seqkeys::~seqkeys ( ) [inline], [virtual]

12.62.2 Member Function Documentation

12.62.2.1 void seq64::seqkeys::set_scale (int *scale*)

This function is called by the seqedit class.

Parameters

scale	The musical scale value to be set.

12.62.2.2 void seq64::seqkeys::set_key (int *key*)

Parameters

key	The musical key value to be set.

12.62.2.3 void seq64::seqkeys::set_hint_key (int *key*)

If m_hint_state is true, the key is drawn (again).

Parameters

key	The key value to set the hint-key to.

12.62.2.4 void seq64::seqkeys::set_hint_state (bool *state*)

Parameters

state	Provides the value for hinting, where true == on, false == off.

12.62.2.5 void seq64::seqkeys::force_draw ( ) [private], [virtual]

Unlike most other overridden versions of force_draw(), this one does not call the base-class version.

Reimplemented from seq64::gui_drawingarea_gtk2.

12.62.2.6 void seq64::seqkeys::draw_area ( ) [private]

12.62.2.7 void seq64::seqkeys::update_pixmap ( ) [private]

This function draws the keys, which range from 0 to 127 (SEQ64_MIDI_COUNT_MAX - 1 = c_num_keys - 1). Every octave, a key letter and number (e.g. "C4") is shown. The letter is adjusted to match the current scale (e.g. "C#4").

We want to support an option to show the key number rather than the note letter/number combination, and perhaps to toggle between them. The current difficulty is that the fonts used are just a little to high to fit within the vertical limits of each key. We really don't want to change the vertical size at this time, so we just print every other note value.

Also note that this algorithm draws from the top down, so we have to account for that.

12.62.2.8 void seq64::seqkeys::convert_y (int *y*, int & *note*) [private]

Parameters

	y	The y (vertical) screen coordinate to convert.
out	*note*	The destination for the note calculation. This would be better as a return value.

12.62.2.9 void seq64::seqkeys::draw_key (int *key*, bool *state*) [private]

It accounts for the black keys and the white keys, and for the highlighting of the active key.

Parameters

key	The key to be drawn.
state	How the key is to be drawn, where false == normal, true == grayed. A key is greyed when the mouse cursor is at the same vertical location on the piano as the key.

12.62.2.10 void seq64::seqkeys::change_vert ( ) [private]

Weird, in seq24 and here, the following was used, completely by accident! We fixed it, but must beware!

```
m_scroll_offset_y = m_scroll_offset_key * c_key_y,  // comma operator!!!
force_draw();
```

12.62.2.11 void seq64::seqkeys::update_sizes ( ) [private]

12.62.2.12 void seq64::seqkeys::reset ( ) [private]

12.62.2.13 bool seq64::seqkeys::is_black_key (int *key*) const [inline], [private]

Parameters

key	The key to analyze.

Returns

Returns true if the key is black (value 1, 3, 6, 8, or 10).

12.62.2.14 void seq64::seqkeys::on_realize ( ) [private]

Call the base-class version and then allocates resources that could not be allocated in the constructor. It connects the change_vert() function and then calls it.

12.62.2.15 bool seq64::seqkeys::on_expose_event (GdkEventExpose * *ev*) [private]

Parameters

ev	The expose-event object.

12.62.2.16 bool seq64::seqkeys::on_button_press_event (GdkEventButton * *ev*) [private]

It handles the left and right buttons. The left button, pressed on the piano keyboard, causes m_keying to be set to true, and the given note to play. The right button toggles the note display between letter/number and MIDI note number.

Parameters

ev	The mouse-button event to use.

Returns

Always returns true.

12.62.2.17 bool seq64::seqkeys::on_button_release_event (GdkEventButton * *ev*) [private]

It currently handles only the left button, and only if m_keying is true.

This function is used after pressing on one of the keys on the left-side piano keyboard, to make it play, and turns off the playing of the note.

Parameters

ev	The button-event.

Returns

Always returns true.

12.62.2.18 bool seq64::seqkeys::on_motion_notify_event (GdkEventMotion * *p0*) [private]

This allows rolling down the keyboard, playing the notes one-by-one.

Parameters

p0	The motion event.

Returns

Always returns false.

12.62.2.19 bool seq64::seqkeys::on_enter_notify_event (GdkEventCrossing * *p0*) [private]

This greys the current key.

12.62.2.20 bool seq64::seqkeys::on_leave_notify_event (GdkEventCrossing * *p0*) [private]

This un-greys the current key and stops playing the note.

12.62.2.21 bool seq64::seqkeys::on_scroll_event (GdkEventScroll * *ev*) [private]

Note that there is no usage of the modifier keys (e.g. Shift or Ctrl). Compare this function to seqedit::on_scroll_event().

Parameters

ev	Provides the direction of the scroll event.

Returns

Always returns true.

12.62.2.22 void seq64::seqkeys::on_size_allocate (Gtk::Allocation & *all*) [private]

Parameters

all	Provies the allocation and its width and height.

12.62.3 Field Documentation

12.62.3.1 sequence& seq64::seqkeys::m_seq [private]

12.62.3.2 int seq64::seqkeys::m_scroll_offset_key [private]

Modified in change_vert().

12.62.3.3 int seq64::seqkeys::m_scroll_offset_y [private]

Modified in change_vert().

12.62.3.4 bool seq64::seqkeys::m_hint_state [private]

12.62.3.5 int seq64::seqkeys::m_hint_key [private]

12.62.3.6 bool seq64::seqkeys::m_keying [private]

Used in playing the sound for each note as it is clicked in the seqkeys pane.

12.62.3.7 int seq64::seqkeys::m_keying_note [private]

12.62.3.8 int seq64::seqkeys::m_scale [private]

12.62.3.9 int seq64::seqkeys::m_key [private]

12.62.3.10 bool seq64::seqkeys::m_show_octave_letters [private]

If false, then the MIDI key numbers are shown instead. This is a new feature of Sequencer64.

12.63 seq64::seqmenu Class Reference

This class handles the right-click menu of the sequence slots in the pattern window.

Inheritance diagram for seq64::seqmenu:



Public Member Functions

- seqmenu (perform &a_p)

  Principal constructor.
- virtual ~seqmenu ()

  Provides a rote base-class destructor.
- int current_seq () const

'Getter' function for member m_current_seq We're changing the name, so that "seq" indicates an integer by (an imperfect) convention.

- bool is_modified () const

  'Getter' function for member m_modified

Protected Member Functions

- void current_seq (int seq)

  'Setter' function for member m_current_seq
- void set_edit_sequence (int seqnum)

  'Setter' function for member m_edit_sequence Pass in -1 to disable the edit-sequence number.
- void unset_edit_sequence (int seqnum)

  'Setter' function for member m_edit_sequence Disable the edit-sequence number if it matches the parameter.
- bool is_edit_sequence (int seqnum) const

  'Getter' function for member m_edit_sequence Tests the parameter against m_edit_sequence.
- void is_modified (bool flag)

  'Setter' function for member m_modified
- sequence * get_current_sequence () const

  'Getter' function for member m_mainperf.get_sequence(current_seq()) This call is used many, many times, and well worth wrapping.
- sequence * get_sequence (int seqnum) const

  Forwards the get-sequence call to the perform object.
- bool is_current_seq_active () const

  Forwards the is-sequence-active check to the perform object.
- bool is_current_seq_in_edit () const

  Forwards the is-sequence-in-edit check to the perform object.
- void new_current_sequence ()

  Forwards the new-current-sequence call to the perform object.
- void new_sequence (int seqnum)

  Forwards the new-sequence call to the perform object.
- void delete_current_sequence ()

  Forwards the delete-sequence call to the perform object.
- void toggle_current_sequence ()

  Forwards the sequence-playing-toggle call to the perform object.
- void popup_menu ()

  This function sets up the pattern menu entries.
- void seq_edit ()

  This menu callback launches the sequence-editor (pattern editor) window.
- void seq_event_edit ()

  This menu callback launches the new event editor window.
- virtual void seq_set_and_edit (int seqnum)

  Sets the current sequence and then acts as if the user had clicked on its slot.
- virtual void seq_set_and_eventedit (int seqnum)

  Sets the current sequence and then acts as if the user had right-clicked on its slot and selected "Event Edit".

Private Member Functions

- void seq_new ()

  This function sets the new sequence into the perform object, a bit prematurely, though.
- void seq_copy ()

  Copies the selected (current) sequence to the clipboard sequence.
- void seq_cut ()

  Deletes the selected (current) sequence and copies it to the clipboard sequence, if it is not in edit mode.
- void seq_paste ()

  Pastes the sequence clipboard into the current sequence, if the current sequence slot is not active.
- void seq_clear_perf ()

  If the current sequence is active, this function pushes a trigger undo in the main perform object, clears its sequence triggers for the current sequence, and sets the dirty flag of the sequence.
- void set_bus_and_midi_channel (int a_bus, int a_ch)

  Sets up the bus, MIDI channel, and dirtiness flag of the current sequence in the main perform object, as per the give parameters.
- void set_transposable (bool flag)

  Sets the "is-transposable" flag of the current sequence.
- void mute_all_tracks ()

  Mutes all tracks in the main perform object.
- void unmute_all_tracks ()

  Unmutes all tracks in the main perform object.
- void toggle_all_tracks ()

  Toggles the mute-status of all tracks in the main perform object.
- virtual void redraw (int a_sequence)=0
- void on_realize ()

Private Attributes

- Gtk::Menu * m_menu

  The menu to pop up when the right-click action is used either on a mainwid pattern slot or on a perfedit pattern name.
- perform & m_mainperf

  Provides a reference to the central (non-UI) object involved in managing a song and performance.
- sequence m_clipboard

  Holds a copy of data concerning a sequence, which can then be pasted into another pattern slot.
- seqedit * m_seqedit

  Points to the latest seqedit object, if created.
- eventedit * m_eventedit

  Points to the latest eventedit object, if created.
- int m_current_seq

  References the current sequence by sequence number.
- bool m_modified

  Indicates if a sequence has been created.

12.63.1 Detailed Description

It is an abstract base class.

12.63.2 Constructor & Destructor Documentation

12.63.2.1 seq64::seqmenu::seqmenu (perform & *p*)

Apart from filling in some of the members, this function initializes the clipboard, so that we don't get a crash on a paste with no previous copy.

Parameters

p	The main performance object representing the whole MIDI song.

12.63.2.2 seq64::seqmenu::~seqmenu ( ) [virtual]

A rote destructor.

This is necessary in an abstraction base class.

If we determine that we need to delete the m_seqedit pointer, we can do it here. But that is not likely, because we can have many new seqedit objects in play, because we can edit many at once.

12.63.3 Member Function Documentation

12.63.3.1 int seq64::seqmenu::current_seq ( ) const [inline]

12.63.3.2 bool seq64::seqmenu::is_modified ( ) const [inline]

12.63.3.3 void seq64::seqmenu::current_seq (int *seq*) [inline], [protected]

12.63.3.4 void seq64::seqmenu::set_edit_sequence (int *seqnum*) [inline], [protected]

Now a pass-along to the perform object.

12.63.3.5 void seq64::seqmenu::unset_edit_sequence (int *seqnum*) [inline], [protected]

12.63.3.6 bool seq64::seqmenu::is_edit_sequence (int *seqnum*) const [inline], [protected]

Returns true if that member is not -1, and the parameter matches it. Now a pass-along to the perform object.

12.63.3.7 void seq64::seqmenu::is_modified (bool *flag*) [inline], [protected]

12.63.3.8 sequence* seq64::seqmenu::get_current_sequence ( ) const [inline], [protected]

12.63.3.9 sequence* seq64::seqmenu::get_sequence (int *seqnum*) const [inline], [protected]

12.63.3.10 bool seq64::seqmenu::is_current_seq_active ( ) const [inline], [protected]

12.63.3.11 bool seq64::seqmenu::is_current_seq_in_edit ( ) const [inline], [protected]

12.63.3.12 void seq64::seqmenu::new_current_sequence ( ) [inline], [protected]

12.63.3.13 void seq64::seqmenu::new_sequence (int *seqnum*) [inline], [protected]

12.63.3.14 void seq64::seqmenu::delete_current_sequence ( ) [inline], [protected]

12.63.3.15 void seq64::seqmenu::toggle_current_sequence ( ) [inline], [protected]

12.63.3.16 void seq64::seqmenu::popup_menu ( ) [protected]

It also sets up the pattern popup menu entries that are used in mainwid. Note that, for the selected sequence, the "Edit" and "Event Edit" menu entries are not included if a pattern editor or event editor is already running. The new event editor seems to create far-reaching problems that we do not yet understand, so it is now possible to disable it at build time. We have mitigated most of those problems by not allowing both a seq_edit() and a seq_event_edit() at the same time.

12.63.3.17 void seq64::seqmenu::seq_edit ( ) [protected]

If it is already open for that sequence, this function just raises it.

Note that the m_seqedit member to which we save the new pointer is currently there just to avoid a compiler warning.

Also, if a new sequences is created, we set the m_modified flag to true, even though the sequence might later be deleted. Too much modification to keep track of!

An oddity is that calling show_all() here does not work unless the seqedit() constructor makes its show_all() call.

12.63.3.18 void seq64::seqmenu::seq_event_edit ( ) [protected]

If it is already open for that sequence, this function just raises it.

Note that the m_eventedit member to which we save the new pointer is currently there just to avoid a compiler warning.

This menu entry is available only if the selected sequence is active. That is, if the sequence has already been created.

An oddity is that we need the show_all() call here in order to see the dialog. A situation different from that for seqedit! However, now it doesn't seem to be needed, and we have put it back into the eventedit constructor.

12.63.3.19 void seq64::seqmenu::seq_set_and_edit (int *seqnum*) [protected], [virtual]

How do we account for the current screenset? It might not matter if the mute/unmute keystrokes were designed to work only with the current screenset.

Parameters

seqnum	The number of the sequence to edit.

Reimplemented in seq64::mainwid.

12.63.3.20 void seq64::seqmenu::seq_set_and_eventedit (int *seqnum*) [protected], [virtual]

Parameters

seqnum	The number of the sequence to event-edit.

Reimplemented in seq64::mainwid.

12.63.3.21 void seq64::seqmenu::seq_new ( ) [private]

For one thing, if current_seq() is either a -1 or is greater than the maximum allowed sequence number, perform::is_active() will return false, and we have no idea whether the sequence is not active or the sequence number is just invalid. So we need to check the pointer we got before trying to use it.

12.63.3.22 void seq64::seqmenu::seq_copy ( ) [private]

We use a more appropriate function than operator =() here: sequence::partial_assign().

Todo Can be offloaded to a perform member function that accepts a sequence clipboard non-const reference parameter.

12.63.3.23 void seq64::seqmenu::seq_cut ( ) [private]

Todo A lot of seq_cut() can be offloaded to a (new) perform member function that takes a sequence clipboard non-const reference parameter.

12.63.3.24 void seq64::seqmenu::seq_paste ( ) [private]

Then it sets the dirty flag for the destination sequence.

Todo All of seq_paste() can be offloaded to a (new) perform member function with a const clipboard reference parameter.

12.63.3.25 void seq64::seqmenu::seq_clear_perf ( ) [private]

Todo All of seq_paste() can be offloaded to a (new) perform member function.

12.63.3.26 void seq64::seqmenu::set_bus_and_midi_channel (int *bus*, int *ch*) [private]

Parameters

bus	The MIDI buss number to set (bus vs buss? You decide.)
ch	The MIDI channel number to set.

12.63.3.27 void seq64::seqmenu::set_transposable (bool *flag*) [private]

Parameters

flag	The value to use to set the flag.

12.63.3.28 void seq64::seqmenu::mute_all_tracks ( ) [private]

12.63.3.29 void seq64::seqmenu::unmute_all_tracks ( ) [private]

12.63.3.30 void seq64::seqmenu::toggle_all_tracks ( ) [private]

12.63.3.31 virtual void seq64::seqmenu::redraw (int *a_sequence*) [private], [pure virtual]

Implemented in seq64::mainwid, and seq64::perfnames.

12.63.3.32 void seq64::seqmenu::on_realize ( ) [private]

12.63.4 Field Documentation

12.63.4.1 Gtk::Menu* seq64::seqmenu::m_menu [private]

12.63.4.2 perform& seq64::seqmenu::m_mainperf [private]

12.63.4.3 sequence seq64::seqmenu::m_clipboard [private]

12.63.4.4 seqedit* seq64::seqmenu::m_seqedit [private]

Change Note Added by Chris on 2015-08-02 based on compiler warnings and a comment warning in the seq_edit() function. We'll save the result of that function here, and will let valgrind tell us later if Gtkmm takes care of it.

12.63.4.5 eventedit* seq64::seqmenu::m_eventedit [private]

12.63.4.6 int seq64::seqmenu::m_current_seq [private]

12.63.4.7 bool seq64::seqmenu::m_modified [private]

Todo We need to make sure that the perform object is in control of the modification flag.

12.64 seq64::seqroll Class Reference

Implements the piano roll section of the pattern editor.

Inheritance diagram for seq64::seqroll:



Public Member Functions

- seqroll (perform &perf, sequence &seq, int zoom, int snap, seqkeys &seqkeys_wid, int pos, Gtk::Adjustment &hadjust, Gtk::Adjustment &vadjust, int ppqn=SEQ64_USE_DEFAULT_PPQN)

  Principal constructor.
- virtual ~seqroll ()

  Provides a destructor to delete allocated objects.

- void set_snap (int snap)

  Sets the snap to the given value, and then resets the view.
- void set_zoom (int zoom)

  Sets the zoom to the given value, and then resets the view.
- void set_note_length (int note_length)

  'Setter' function for member m_note_length
- int note_off_length () const

  'Getter' function for member m_note_length, adjusted for the note_off_margin.
- bool add_note (midipulse tick, int note, bool paint=true)

  Convenience wrapper for sequence::add_note().
- void set_key (int key)

  Sets the music key to the given value, and then resets the view.
- void set_scale (int scale)

  Sets the music scale to the given value, and then resets the view.
- void set_data_type (midibyte status, midibyte control)

  Sets the status to the given parameter, and the CC value to the given optional control parameter, which defaults to 0.
- void set_background_sequence (bool state, int seq)

  This function sets the given sequence onto the piano roll of the pattern editor, so that the musician can have another pattern to play against.
- void update_pixmap ()

  This function draws the background pixmap on the main pixmap, and then draws the events on it.
- void update_sizes ()

  Update the sizes of items based on zoom, PPQN, BPM, BW (beat width) and more.
- void update_background ()

  Updates the background of this window.
- void draw_background_on_pixmap ()

  Draws the main pixmap.
- void draw_events_on_pixmap ()

  Fills the main pixmap with events.
- void draw_selection_on_window ()

  Draws the current selecton on the main window.
- void draw_progress_on_window ()

  Draw a progress line on the window.
- void reset ()

  This function basically resets the whole widget as if it were realized again.
- void update_and_draw (int force=false)

  Wraps up some common code.
- void redraw ()

  Redraws unless m_ignore_redraw is true.
- void redraw_events ()

  Redraws events unless m_ignore_redraw is true.
- void start_paste ()

  Starts a paste operation.
- void complete_paste ()
- void complete_paste (int x, int y)

  Completes a paste operation.
- void follow_progress ()

Private Member Functions

- virtual void force_draw ()

  Set the pixmap into the window and then draws the selection on it.
- void horizontal_adjust (double step)

  This function provides optimization for the on_scroll_event() function.
- void vertical_adjust (double step)

  This function provides optimization for the on_scroll_event() function.
- void snap_y (int &y)

  Snaps the y value to the piano-key "height".
- void snap_x (int &x)

  Performs a 'snap' operation on the x coordinate.
- void convert_xy (int x, int y, midipulse &ticks, int &note)
- void convert_tn (midipulse ticks, int note, int &x, int &y)

  This function takes the given note and tick, and returns the screen coordinates via the pointer parameters.
- void xy_to_rect (int x1, int y1, int x2, int y2, int &x, int &y, int &w, int &h)

  Converts rectangle corner coordinates to a starting coordinate, plus a width and height.
- void convert_tn_box_to_rect (midipulse tick_s, midipulse tick_f, int note_h, int note_l, int &x, int &y, int &w, int &h)

  Converts a tick/note box to an x/y rectangle.
- void convert_sel_box_to_rect (midipulse tick_s, midipulse tick_f, int note_h, int note_l)

  A convenience function wrapping a common call to convert_tn_box_to_rect().
- void get_selected_box (midipulse &tick_s, int &note_h, midipulse &tick_f, int &note_l)

  A convenience function wrapping a common call to m_seq.get_selected_box() and convert_tn_box_to_rect().
- void draw_events_on (Glib::RefPtr< Gdk::Drawable > draw)

  Draws events on the given drawable area.
- int idle_redraw ()

  Draw the events on the main window and on the pixmap.
- int idle_progress ()
- void change_horz ()

  Change the horizontal scrolling offset and redraw.
- void change_vert ()

  Change the vertical scrolling offset and redraw.
- void move_selection_box (int dx, int dy)

  Function to allow motion of the selection box via the arrow keys.
- void move_selected_notes (int dx, int dy)

  Proposed new function to encapsulate the movement of selections even more fully.
- void grow_selected_notes (int dx)

  Proposed new function to encapsulate the movement of selections even more fully.
- void set_adding (bool adding)

  Changes the mouse cursor pixmap according to whether a note is being added or not.
- void update_mouse_pointer (bool adding=false)

  Updates the mouse pointer, implementing a context-sensitive mouse.
- bool button_press_initial (GdkEventButton *ev, int &norm_x, int &snapped_x, int &snapped_y)
- void align_selection (midipulse &tick_s, int &note_h, midipulse &tick_f, int &note_l, int snapped_x)

  Get the box that selected elements are in.
- bool button_press (GdkEventButton *ev)

  Implements the on-button-press event handling for the Seq24 style of mouse interaction.
- bool button_release (GdkEventButton *ev)

  Implements the on-button-release event handling for the Seq24 style of mouse interaction.
- bool motion_notify (GdkEventMotion *ev)

Seq24-style on-motion mouse interaction.

- void clear_selected ()

  'Setter' function for member m_old

- void clear_old ()

  'Setter' function for member m_old

- void clear_flags ()

  Clears all the mouse-action flags.

- int scroll_offset_x (int x) const

  Useful x calculation.

- int scroll_offset_y (int y) const

  Useful y calculation.

- void set_current_offset_x_y (int x, int y)

  Useful x calculation.

- bool adding () const

  'Getter' function for member m_adding

- bool selecting () const

  'Getter' function for member m_selecting

- bool growing () const

  'Getter' function for member m_growing

- bool normal_action () const

  Indicates if we're drag-pasting, selecting, moving, growing, or pasting.

- bool select_action () const

  Indicates if we're selecting, moving, growing, or pasting.

- bool drop_action () const

  Indicates if we're moving or pasting.

- void on_realize ()

  Implements the on-realize event handling.

- bool on_expose_event (GdkEventExpose *ev)

  Implements the on-expose event handling.

- bool on_button_press_event (GdkEventButton *ev)

  Implements the on-button-press event handling.

- bool on_button_release_event (GdkEventButton *ev)

  Implements the on-button-release event handling.

- bool on_motion_notify_event (GdkEventMotion *ev)

  Implements the on-motion-notify event handling.

- bool on_focus_in_event (GdkEventFocus *)

  Implements the on-focus event handling.

- bool on_focus_out_event (GdkEventFocus *)

  Implements the on-unfocus event handling.

- bool on_key_press_event (GdkEventKey *ev)

  Implements the on-key-press event handling.

- bool on_scroll_event (GdkEventScroll *a_ev)

  Implements the on-scroll event handling.

- void on_size_allocate (Gtk::Allocation &)

  Implements the on-size-allocate event handling.

- bool on_leave_notify_event (GdkEventCrossing *p0)

  Implements the on-leave-notify event handling.

- bool on_enter_notify_event (GdkEventCrossing *p0)

  Implements the on-enter-notify event handling.

Private Attributes

- Gtk::Adjustment & m_horizontal_adjust

  We need direct access to the horizontal scrollbar if we want to be able to make it follow the progress bar.
- Gtk::Adjustment & m_vertical_adjust

  We need direct access to the vertical scrollbar if we want to be able to make it follow PageUp and PageDown.
- rect m_old

  The previous selection rectangle, used for undrawing it.
- rect m_selected

  Used in moving and pasting notes.
- sequence & m_seq

  Provides a reference to the seqeunce represented by piano roll.
- seqkeys & m_seqkeys_wid

  Holds a reference to the seqkeys pane that is associated with the seqroll piano roll.
- FruitySeqRollInput m_fruity_interaction

  Provides a fruity input object, whether it is needed or not.
- int m_pos

  A position value.
- int m_zoom

  Zoom setting, means that one pixel == m_zoom ticks.
- int m_snap

  The grid-snap setting for the piano roll grid.
- int m_ppqn

  The value of PPQN for the current MIDI song.
- int m_note_length

  Holds the note length in force for this sequence.
- int m_scale

  Indicates the musical scale in force for this sequence.
- int m_key

  Indicates the musical key in force for this sequence.
- bool m_adding

  Set when in note-adding mode.
- bool m_selecting

  Set when highlighting a bunch of events.
- bool m_moving

  Set when moving a bunch of events.
- bool m_moving_init

  Indicates the beginning of moving some events.
- bool m_growing

  Indicates that the notes are to be extended or reduced in length.
- bool m_painting

  Indicates the painting of events.
- bool m_paste

  Indicates that we are in the process of painting notes.
- bool m_is_drag_pasting

  Indicates the drag-pasting of events.
- bool m_is_drag_pasting_start

  Indicates the drag-pasting of events.
- bool m_justselected_one

  Indicates the selection of one event.
- int m_move_delta_x

Tells where the dragging started, the x value.

- int m_move_delta_y

  Tells where the dragging started, the y value.

- int m_move_snap_offset_x

  This item is used in the fruityseqroll module.

- int m_progress_x

  Provides the location of the progress bar.

- int m_scroll_offset_ticks

  The horizontal value of the scroll window in units of ticks/pulses/divisions.

- int m_scroll_offset_key

  The vertical offset of the scroll window in units of MIDI notes/keys.

- int m_scroll_offset_x

  The horizontal value of the scroll window in units of pixels.

- int m_scroll_offset_y

  The vertical value of the scroll window in units of pixels.

- int m_background_sequence

  Holds the value of the musical background sequence that is shown in cyan (formerly grey) on the background of the piano roll.

- bool m_drawing_background_seq

  Set to true if the drawing of the background sequence is to be done.

- midibyte m_status

  Set to true to avoid the call to update_and_draw().

- midibyte m_cc

  The current MIDI control value selected in the seqedit.

Friends

- class FruitySeqRollInput

  This friend implements fruity interaction-specific behavior.

Additional Inherited Members

12.64.1 Constructor & Destructor Documentation

12.64.1.1 seq64::seqroll::seqroll (perform & *p*, sequence & *seq*, int *zoom*, int *snap*, seqkeys & *seqkeys_wid*, int *pos*, Gtk::Adjustment & *hadjust*, Gtk::Adjustment & *vadjust*, int *ppqn* = SEQ64_USE_DEFAULT_PPQN)

Parameters

p	The performance object that helps control this piano roll. Note that we can get the perform object from the sequence, and save a parameter. Low priority change.
seq	The sequence object represented by this piano roll.
zoom	The initial zoom of this piano roll.
snap	The initial grid snap of this piano roll.
seqkeys_wid	A reference to the piano keys window that is shown to the left of this piano roll.
pos	A position parameter. See the description of seqroll::m_pos. This is actually the sequence number, and is currently unused. However, we're sure we can find a use for it sometime.
hadjust	Represents the horizontal scrollbar of this window. It is actually created by the "parent" seqedit object.
vadjust	Represents the vertical scrollbar of this window. It is actually created by the "parent" seqedit object.
ppqn	The initial value of the PPQN for this sequence. Useful in scale calculations.

12.64.1.2 seq64::seqroll::~seqroll ( ) [virtual]

The only thing to delete here is the clipboard. Except it is never used, so is commented out.

12.64.2 Member Function Documentation

12.64.2.1 void seq64::seqroll::set_snap (int *snap*) [inline]

Parameters

snap	Provides the sname value to set.

12.64.2.2 void seq64::seqroll::set_zoom (int *zoom*)

Parameters

zoom	The desired zoom value.

12.64.2.3 void seq64::seqroll::set_note_length (int *note_length*) [inline]

12.64.2.4 int seq64::seqroll::note_off_length ( ) const [inline]

12.64.2.5 bool seq64::seqroll::add_note (midipulse *tick*, int *note*, bool *paint* = true)

The length parameters is obtained from the note_off_length() function. This sets the note length at a little less than the snap value.

Parameters

tick	The time destination of the new note, in pulses.
note	The pitch destination of the new note.
paint	If true, repaint to be left with just the inserted event. The default is true. The value of false is useful in inserting a number of events and saving the repainting until last. It is a bit tricky, as the default paint value for sequence::add_note() is false.

12.64.2.6 void seq64::seqroll::set_key (int *key*)

Parameters

key	The desired key value.

12.64.2.7 void seq64::seqroll::set_scale (int *scale*)

Parameters

scale	The desired scale value.

12.64.2.8 void seq64::seqroll::set_data_type (midibyte *status*, midibyte *control*) [inline]

Unlike the same function in seqevent, this version does not redraw. Used by seqedit.

12.64.2.9 void seq64::seqroll::set_background_sequence (bool *state*, int *seq*)

The state parameter sets the boolean m_drawing_background_seq.

Parameters

state	If true, the background sequence will be drawn.
seq	Provides the sequence number, which is checked against the SEQ64_IS_LEGAL_SEQUENCE() macro before being used. This macro allows the value SEQ64_SEQUENCE_LIMIT, which disables the background sequence.

12.64.2.10 void seq64::seqroll::update_pixmap ( )

12.64.2.11 void seq64::seqroll::update_sizes ( )

It brings the scrollbar back to the beginning, resets the upper limit to the number of ticks in the sequence, sets the page-size based on the window size and the zoom factor.

The horizontal step increment is 1 semiquaver (1/16) note per zoom level. The horizontal page increment is currently always one bar. We may want to make that larger for scrolling after the progress bar.

Tha maximum value set for the scrollbar brings it to the last "page" of the piano roll.

The vertical size are also adjusted. More on the story later.

12.64.2.12 void seq64::seqroll::update_background ( )

The first thing done is to clear the background, painting it white.

12.64.2.13 void seq64::seqroll::draw_background_on_pixmap ( )

12.64.2.14 void seq64::seqroll::draw_events_on_pixmap ( )

Just calls draw_events_on().

12.64.2.15 void seq64::seqroll::draw_selection_on_window ( )

Note the parameters of draw_drawable(), which we need to be sure of to draw thicker boxes.

```
-   x and y position of rectangle to draw
-   x and y position in drawable where rectangle should be drawn
-   width and height of rectangle to draw
```

A final parameter of false draws an unfilled rectangle. Orange makes it a little more clear that we're pasting, I think. We also want to try to thicken the lines somehow.

12.64.2.16 void seq64::seqroll::draw_progress_on_window ( )

This is done by first blanking out the line with the background, which contains white space and grey lines, using the the draw_drawable function. Remember that we wrap the draw_drawable() function so it's parameters are xsrc, ysrc, xdest, ydest, width, and height.

Note that the progress-bar position is based on the sequence::get_last_tick() value, the current zoom, and the current scroll-offset x value.

Finally, we had an issue with the selection box flickering, which seems to be solved satisfactorily by not drawing it if a select action is in force. Hopefully no one needs to select notes on the fly and see the progress bar moving at the same time! Another tactic is to draw progress only when the performance is running. This has the benefit/drawback that the progress bar is left where it stops. Consider an enumeration of options: normal, when-not-selecting, and when-running.

12.64.2.17 void seq64::seqroll::reset ( )

It's almost identical to the change_horz() function, just calling update_sizes() before update_and_draw().

12.64.2.18 void seq64::seqroll::update_and_draw (int *force* = `false`)

Parameters

force	If true, force an immediate draw, otherwise just queue up a draw.

12.64.2.19 void seq64::seqroll::redraw ( )

Somewhat similar to seqevent::redraw(). Actually, we don't seem to need to ignore redraw when making settings in the seqedit constructor, so this member no longer exists.

12.64.2.20 void seq64::seqroll::redraw_events ( )

Actually, that member is not needed and no longer exists.

12.64.2.21 void seq64::seqroll::start_paste ( )

12.64.2.22 void seq64::seqroll::complete_paste ( ) [inline]

12.64.2.23 void seq64::seqroll::complete_paste (int *x*, int *y*)

12.64.2.24 void seq64::seqroll::follow_progress ( ) [inline]

12.64.2.25 void seq64::seqroll::force_draw ( ) [private], [virtual]

Reimplemented from seq64::gui_drawingarea_gtk2.

12.64.2.26 void seq64::seqroll::horizontal_adjust (double *step*) [inline], [private]

A duplicate of the one in seqedit.

Parameters

step	Provides the step value to use for adjusting the horizontal scrollbar. See gui_drawingarea_gtk2::scroll_hadjust() for more information.

12.64.2.27 void seq64::seqroll::vertical_adjust (double *step*) [inline], [private]

A duplicate of the one in seqedit.

Parameters

step	Provides the step value to use for adjusting the vertical scrollbar. See gui_drawingarea_gtk2::scroll_vadjust() for more information.

12.64.2.28 void seq64::seqroll::snap_y (int & *y*) [inline], [private]

Parameters

out	*y*	The y-value to be snapped.

12.64.2.29 void seq64::seqroll::snap_x (int & *x*) [private]

This function is similar to snap_y(), but it calculates a modulo value from the snap and zoom settings.

```
-   m_snap = number pulses to snap to
-   m_zoom = number of pulses per pixel
```

Therefore, m_snap / m_zoom = number pixels to snap to.

Parameters

out	*x*	Provides the x-value to be snapped and returned. A return value would be better.

12.64.2.30 void seq64::seqroll::convert_xy (int *x*, int *y*, midipulse & *ticks*, int & *note*) [private]

12.64.2.31 void seq64::seqroll::convert_tn (midipulse *tick*, int *note*, int & *x*, int & *y*) [private]

This function is the "inverse" of convert_xy().

Parameters

	tick	Provides the horizontal value in MIDI pulses.
	note	Provides the vertical value, a note value.
out	*x*	Provides the destination x value of the coordinate.
out	*y*	Provides the destination y value of the coordinate.

12.64.2.32 void seq64::seqroll::xy_to_rect (int *x1*, int *y1*, int *x2*, int *y2*, int & *x*, int & *y*, int & *w*, int & *h*) [private]

This function checks the mins / maxes, and then fills in the x, y, width, and height values.

We should refactor this function to use the utility class seqroll::rect as the destination for the conversion.

Parameters

	x1	The x value of the first corner.
	y1	The y value of the first corner.
	x2	The x value of the second corner.
	y2	The y value of the second corner.
out	*x*	The destination for the x value in pixels.
out	*y*	The destination for the y value in pixels.
out	*w*	The destination for the rectangle width in pixels.
out	*h*	The destination for the rectangle height value in pixels.

12.64.2.33 void seq64::seqroll::convert_tn_box_to_rect (midipulse *tick_s*, midipulse *tick_f*, int *note_h*, int *note_l*, int & *x*, int & *y*, int & *w*, int & *h*) [private]

We should refactor this function to use the utility class seqroll::rect as the destination for the conversion.

Parameters

	tick_s	The starting tick of the rectangle.
	tick_f	The finishing tick of the rectangle.
	note_h	The high note of the rectangle.

Parameters

	note_l	The low note of the rectangle.
out	*x*	The destination for the x value in pixels.
out	*y*	The destination for the y value in pixels.
out	*w*	The destination for the rectangle width in pixels.
out	*h*	The destination for the rectangle height value in pixels.

12.64.2.34 void seq64::seqroll::convert_sel_box_to_rect (midipulse *tick_s*, midipulse *tick_f*, int *note_h*, int *note_l*) [private]

Parameters

tick_s	The starting tick of the rectangle.
tick_f	The finishing tick of the rectangle.
note_h	The high note of the rectangle.
note_l	The low note of the rectangle.

12.64.2.35 void seq64::seqroll::get_selected_box (midipulse & *tick_s*, int & *note_h*, midipulse & *tick_f*, int & *note_l*) [private]

Parameters

out	*tick_s*	The starting tick of the rectangle.
out	*tick_f*	The finishing tick of the rectangle.
out	*note_h*	The high note of the rectangle.
out	*note_l*	The low note of the rectangle.

12.64.2.36 void seq64::seqroll::draw_events_on (Glib::RefPtr< Gdk::Drawable > *draw*) [private]

"Method 0" draws the background sequence, if active. "Method 1" draws the sequence itself.

Parameters

draw	The "drawable" area to draw on.

12.64.2.37 int seq64::seqroll::idle_redraw ( ) [private]

12.64.2.38 int seq64::seqroll::idle_progress ( ) [private]

12.64.2.39 void seq64::seqroll::change_horz ( ) [private]

Roughly similar to seqevent::change_horz().

12.64.2.40 void seq64::seqroll::change_vert ( ) [private]

12.64.2.41 void seq64::seqroll::move_selection_box (int *dx,* int *dy*) [private]

We now let the Enter key to finish pasting and deselect the moved notes. With the mouse, selecting all notes, copying them, and moving the selection box, pasting can be completed with either a left-click or the Enter key.

We have a weird problem on our main system where the selection box is very flickery. But it works fine on another system. A Gtk-2 issue? Now it seems to work fine, after an update. No, it seems to work well in sequences that have non-note events amongst the note events.

Parameters

dx	The amount to move the selection box. Values are -1, 0, or 1. -1 is left one snap, 0 is no movement horizontally, and 1 is right one snap.
dy	The amount to move the selection box. Values are -1, 0, or 1. -1 is up one snap, 0 is no movement vertically, and 1 is down one snap.

12.64.2.42 void seq64::seqroll::move_selected_notes (int *dx,* int *dy*) [private]

Works with the four arrow keys.

Note that the movement vertically is different for the selection box versus the notes. While the movement values are -1, 0, or 1, the differences are as follows:

```
-   Selection box vertical movement:
    -   -1 is up one note snap.
    -   0 is no vertical movement.
    -   +1 is down one note snap.
-   Note vertical movement:
    -   -1 is down one note.
    -   0 is no note vertical movement.
    -   +1 is up one note.
```

Parameters

dx	The amount to move the selection box or the selection horizontally. Values are -1 (left one time snap), 0 (no movement), and +1 (right one snap). Obviously values other than +-1 can be used for larger movement, but the GUI doesn't yet support that ... we could implement movement by "pages" some day.
dy	The amount to move the selection box or the selection vertically. See the notes above.

12.64.2.43 void seq64::seqroll::grow_selected_notes (int *dx*) [private]

Parameters

dx	The amount to grow the selection horizontally. Values are -1 (left one time snap), 0 (no stretching), and +1 (right one snap). Obviously values other than +-1 can be used for larger stretching, but the GUI doesn't yet support that.

12.64.2.44 void seq64::seqroll::set_adding (bool *adding*) [private]

What calls this? It is actually a right click. Not present in the "fruity" implementation. Now moved to the normal seqroll class.

Parameters

adding	True if adding a note.

12.64.2.45 void seq64::seqroll::update_mouse_pointer (bool *adding* = false) [private]

Moved here from the "fruity" seqroll class.

12.64.2.46 bool seq64::seqroll::button_press_initial (GdkEventButton * *ev*, int & *norm_x*, int & *snapped_x*, int & *snapped_y*) [private]

12.64.2.47 void seq64::seqroll::align_selection (midipulse & *tick_s*, int & *note_h*, midipulse & *tick_f*, int & *note_l*, int *snapped_x*) [private]

Save offset that we get from the snap above. Align selection for drawing. Could be used in XRollInput::on_button↩
_press_event().

12.64.2.48 bool seq64::seqroll::button_press (GdkEventButton * *ev*) [private]

This function now uses the needs_update flag to determine if the perform object should modify().

Parameters

ev	Provides the button-press event to process.

Returns

Returns the value of needs_update. It used to return only true.

12.64.2.49 bool seq64::seqroll::button_release (GdkEventButton * *ev*) [private]

This function now uses the needs_update flag to determine if the perform object should modify().

Parameters

ev	Provides the button-release event to process.

Returns

Returns the value of needs_update. It used to return only true.

If in moving mode, adjust for snap and convert deltas into screen coordinates. Since delta_note was from delta_y, it will be flipped (delta_y[0] = note[127], etc.), so we have to adjust.

A left/middle click converts deltas into screen coordinates, then pushs the undo state. Shift causes a "stretch selected" which currently acts like a "move selected" operation. BUG? Otherwise, Ctrl indirectly allows a "grow selected" operation.

Minor new feature. If the Super (Mod4, Windows) key is pressed when release, keep the adding state in force. One can then use the unadorned left-click key to add notes. Right click to reset the adding mode. This feature is enabled only if allowed by the settings (but is true by default). See the same code in perfrollinput.cpp.

12.64.2.50 bool seq64::seqroll::motion_notify (GdkEventMotion * *ev*) [private]

We could allow move painting for chords, but that would take some tricky code to move all of the notes of the chord. And allowing painting here currently affects only one note after the chord itself is created.

Parameters

ev	Provides the button-release event to process.

Returns

Returns true if the event was processed.

12.64.2.51 void seq64::seqroll::clear_selected ( ) [inline], [private]

12.64.2.52 void seq64::seqroll::clear_old ( ) [inline], [private]

12.64.2.53 void seq64::seqroll::clear_flags ( ) [inline], [private]

12.64.2.54 int seq64::seqroll::scroll_offset_x (int *x*) const [inline], [private]

Offsets the x value by the x origin of the current page.

Parameters

x	The x value to offset.

12.64.2.55 int seq64::seqroll::scroll_offset_y (int *y*) const [inline], [private]

Offsets the y value by the y origin of the current page.

Parameters

y	The y value to offset.

12.64.2.56 void seq64::seqroll::set_current_offset_x_y (int *x*, int *y*) [inline], [private]

Offsets the current x value by the x origin of the current page.

Parameters

x	The x value to offset.

void set_current_offset_x (int x) { m_current_x = x + m_scroll_offset_x; } Useful y calculation. Offsets the current y value by the y origin of the current page.

Parameters

y	The y value to offset.

void set_current_offset_y (int y) { m_current_y = y + m_scroll_offset_y; } Useful x and y calculation. Offsets the current x and y values by the x and y origin of the current page.

Parameters

x	The y value to offset.
y	The y value to offset.

12.64.2.57 bool seq64::seqroll::adding ( ) const [inline], [private]

12.64.2.58 bool seq64::seqroll::selecting ( ) const [inline], [private]

12.64.2.59 bool seq64::seqroll::growing ( ) const [inline], [private]

12.64.2.60 bool seq64::seqroll::normal_action ( ) const [inline], [private]

Returns

Returns true if one of those five flags are set.

12.64.2.61 bool seq64::seqroll::select_action ( ) const [inline], [private]

Returns

Returns true if one of those four flags are set.

12.64.2.62 bool seq64::seqroll::drop_action ( ) const [inline], [private]

Returns

Returns true if one of those two flags are set.

12.64.2.63 void seq64::seqroll::on_realize ( ) [private]

12.64.2.64 bool seq64::seqroll::on_expose_event (GdkEventExpose * *ev*) [private]

Parameters

ev	The expose event to process.

Returns

Always returns true.

12.64.2.65 bool seq64::seqroll::on_button_press_event (GdkEventButton * *ev*) [private]

Parameters

ev	The expose event to process.

Returns

Returns the result of the Seq24 interaction or the Fruity interaction, that is, the return value of Seq24SeqRollInput::on_button_press_event() or FruitySeqRollInput::on_button_press_event().

12.64.2.66 bool seq64::seqroll::on_button_release_event (GdkEventButton * *ev*) [private]

This function checks the "rc" interaction-method option, and calls the forwarding function for the seq24 or the fruity interaction method. Might be a good case to prefer inheritance and not try to support changing the interaction method without a restart of Sequencer64.

Parameters

ev	The button release event to process.

Returns

Returns the return value of Seq24SeqRollInput::on_button_release_event() or FruitySeqRollInput::on_button_release_event().

12.64.2.67 bool seq64::seqroll::on_motion_notify_event (GdkEventMotion * *ev*) [private]

Parameters

ev	The motion-notification event to process.

Returns

Returns the return value of Seq24SeqRollInput::on_motion_notify_event() or FruitySeqRollInput::on_motion_notify_event().

12.64.2.68 bool seq64::seqroll::on_focus_in_event (GdkEventFocus *) [private]

Sets the GDK HAS_FOCUS flag. Parameter "ev" is the event-focus event, not used.

Returns

Always returns false.

12.64.2.69 bool seq64::seqroll::on_focus_out_event (GdkEventFocus *) [private]

Resets the GDK HAS_FOCUS flag. Parameter "ev" is the event-focus event, not used.

Returns

Always returns false.

12.64.2.70 bool seq64::seqroll::on_key_press_event (GdkEventKey * *ev*) [private]

The start/end key may be the same key (i.e. SPACEBAR). Allow toggling when the same key is mapped to both triggers (i.e. SPACEBAR).

Concerning the usage of the arrow keys in this function: This code is reached, but has no visible effect. Why? I think they were meant to move the point for playback. We may have a bug with our new handling of triggers (unlikely), or maybe these depend upon the proper playback mode. In any case, the old functionality is preserved. However, if there are notes selected, then these keys support selection movement.

Since the Up and Down arrow keys are used for movement, we'd have to check selection status before trying to use them to move up and down in the piano roll, in smaller steps than the new Page-Up and Page-Down key support.

Parameters

ev	The key-press event to process.

Returns

Returns true if the key-press was handled.

I think we should be able to move and remove notes while playing, which is already supported using the mouse.

if (! perf().is_playing)

12.64.2.71 bool seq64::seqroll::on_scroll_event (GdkEventScroll * *ev*) [private]

This scroll event only handles basic scrolling without any modifier keys such as the Ctrl or Shift masks. The seqedit class handles that fun stuff.

Note that this function seems to duplicate the functionality of seqkeys::on_scroll_event(). Do we really need both? Which one do we need?

Parameters

ev	The scroll event to process.

Returns

Returns true if the scroll event was handled.

12.64.2.72 void seq64::seqroll::on_size_allocate (Gtk::Allocation & *a*) [private]

Calls the base-class version of this function and sets m_window_x and m_window_y to the width and height of the allocation parameter. Then calls update_sizes().

Parameters

a	The GDK allocation event object.

12.64.2.73 bool seq64::seqroll::on_leave_notify_event (GdkEventCrossing * *p0*) [private]

Calls m_seqkeys_wid.set_hint_state(false). Parameter "ev" is the event-crossing event, not used.

Returns

Always returns false.

12.64.2.74 bool seq64::seqroll::on_enter_notify_event (GdkEventCrossing * *p0*) [private]

Calls m_seqkeys_wid.set_hint_state(true). Parameter "ev" is the event-crossing event, not used.

Returns

Always returns false.

12.64.3 Friends And Related Function Documentation

12.64.3.1 friend class FruitySeqRollInput [friend]

We've absorbed the Seq24SeqRollInput class functionality back into seqroll, to save code.

12.64.4 Field Documentation

12.64.4.1 Gtk::Adjustment& seq64::seqroll::m_horizontal_adjust [private]

12.64.4.2 Gtk::Adjustment& seq64::seqroll::m_vertical_adjust [private]

12.64.4.3 rect seq64::seqroll::m_old [private]

12.64.4.4 rect seq64::seqroll::m_selected [private]

12.64.4.5 sequence& seq64::seqroll::m_seq [private]

12.64.4.6 seqkeys& seq64::seqroll::m_seqkeys_wid [private]

12.64.4.7 FruitySeqRollInput seq64::seqroll::m_fruity_interaction [private]

12.64.4.8 int seq64::seqroll::m_pos [private]

Need to clarify what exactly this member is used for.

12.64.4.9 int seq64::seqroll::m_zoom [private]

12.64.4.10 int seq64::seqroll::m_snap [private]

Same meaning as for the event-bar grid. This value is the denominator of the note size used for the snap.

12.64.4.11 int seq64::seqroll::m_ppqn [private]

Supports values other than the default of 192.

12.64.4.12 int seq64::seqroll::m_note_length [private]

Used in the seq24seqroll module only.

12.64.4.13 int seq64::seqroll::m_scale [private]

12.64.4.14 int seq64::seqroll::m_key [private]

12.64.4.15 bool seq64::seqroll::m_adding [private]

This flag was moved from both the fruity and the seq24 seqroll classes.

12.64.4.16 bool seq64::seqroll::m_selecting [private]

12.64.4.17 bool seq64::seqroll::m_moving [private]

12.64.4.18 bool seq64::seqroll::m_moving_init [private]

Used in the fruity and seq24 mouse-handling modules.

12.64.4.19 bool seq64::seqroll::m_growing [private]

12.64.4.20 bool seq64::seqroll::m_painting [private]

Used in the fruity and seq24 mouse-handling modules.

12.64.4.21 bool seq64::seqroll::m_paste [private]

12.64.4.22 bool seq64::seqroll::m_is_drag_pasting [private]

Used in the fruity mouse-handling module.

12.64.4.23 bool seq64::seqroll::m_is_drag_pasting_start [private]

Used in the fruity mouse-handling module.

12.64.4.24 bool seq64::seqroll::m_justselected_one [private]

Used in the fruity mouse-handling module.

12.64.4.25 int seq64::seqroll::m_move_delta_x [private]

12.64.4.26 int seq64::seqroll::m_move_delta_y [private]

12.64.4.27 int seq64::seqroll::m_move_snap_offset_x [private]

12.64.4.28 int seq64::seqroll::m_progress_x [private]

12.64.4.29 int seq64::seqroll::m_scroll_offset_ticks [private]

12.64.4.30 int seq64::seqroll::m_scroll_offset_key [private]

12.64.4.31 int seq64::seqroll::m_scroll_offset_x [private]

12.64.4.32 int seq64::seqroll::m_scroll_offset_y [private]

12.64.4.33 int seq64::seqroll::m_background_sequence [private]

12.64.4.34 bool seq64::seqroll::m_drawing_background_seq [private]

12.64.4.35 midibyte seq64::seqroll::m_status [private]

Used in set_background_sequence(), change_horz(), change_vert(), reset().... Never set to true, except in seq24, let's just comment it out for now. It hasn't been used in sequencer64 for awhile now.

bool m_ignore_redraw; The current status/event selected in the seqedit. Not used in seqroll at present.

12.64.4.36 midibyte seq64::seqroll::m_cc [private]

Not used in seqroll at present.

12.65 seq64::seqtime Class Reference

This class implements the piano time, whatever that is.

Inheritance diagram for seq64::seqtime:



Public Member Functions

- seqtime (sequence &seq, perform &p, int zoom, Gtk::Adjustment &hadjust, int ppqn=SEQ64_USE_DEFA↩ ULT_PPQN)

  Principal constructor.
- virtual ~seqtime ()

  Let's provide a do-nothing virtual destructor.
- void reset ()

  Sets the scroll offset tick and x values, updates the sizes and the pixmap, and resets the window.
- void redraw ()

  Very similar to the reset() function, except it doesn't update the sizes.
- void set_zoom (int zoom)

  Sets the zoom to the given value and resets the window.

Private Member Functions

- void draw_pixmap_on_window ()

  Draws the pixmap on the window.
- void draw_progress_on_window ()
- void update_pixmap ()

  Updates the pixmap.
- void change_horz ()

  Changes the scrolling horizontal offset, updates the pixmap, and forces a redraw.
- void update_sizes ()

  Updates the pixmap to a new size and queues up a draw operation.
- bool idle_progress ()

  Simply returns true.
- void on_realize ()

  Called when the window is drawn.
- bool on_expose_event (GdkEventExpose *a_ev)

  Implements the on-expose event handler.
- void on_size_allocate (Gtk::Allocation &)

  Implements the on-size-allocate event handler.
- bool on_button_press_event (GdkEventButton *)

  Implements the on-button-press event handler.
- bool on_button_release_event (GdkEventButton *)

  Implements the on-button-release event handler.

Private Attributes

- sequence & m_seq
- int m_scroll_offset_ticks
- int m_scroll_offset_x
- int m_zoom

  one pixel == m_zoom ticks
- int m_ppqn

Additional Inherited Members

12.65.1 Constructor & Destructor Documentation

12.65.1.1 seq64::seqtime::seqtime (sequence & *seq,* perform & *p,* int *zoom,* Gtk::Adjustment & *hadjust,* int *ppqn =* SEQ64_USE_DEFAULT_PPQN)

In the constructor you can only allocate colors; get_window() returns 0 because the window is not yet realized>

12.65.1.2 virtual seq64::seqtime::~seqtime ( ) [inline], [virtual]

12.65.2 Member Function Documentation

12.65.2.1 void seq64::seqtime::reset ( )

Basically identical to seqevent::reset().

12.65.2.2 void seq64::seqtime::redraw ( )

12.65.2.3 void seq64::seqtime::set_zoom (int *zoom*)

12.65.2.4 void seq64::seqtime::draw_pixmap_on_window ( ) [private]

12.65.2.5 void seq64::seqtime::draw_progress_on_window ( ) [private]

12.65.2.6 void seq64::seqtime::update_pixmap ( ) [private]

When the zoom is at 32 ticks per pixel, there is a thick bar for every measure, and a measure number and major time division every 4 measures.at the default PPQN of 192.

A major line is a line that has a measure number in the timeline. The number of measures in a major line is 1 for zooms from 1:1 to 1:8; 2 for zoom 1:16; 4 for zoom 1:32; 8 for zoom 1:64 (new); and 16 for zoom 1:128. Zooms 1:64 and above look good only for high PPQN values.

We calculate the measure length in 32nd notes. This value is, of course, 32, when the time signature is 4/4. Then calculate measures/line. "measures_per_major" is more like "measures per major line". With a higher zoom than 32, this calculation yields a floating-point exception if m_zoom

32, so we rearrange the calculation and hope that it still works out the

same for smaller values.

Todo Sizing needs to be controlled by font parameters. Instead of 19 or 20, estimate the width of 3 letters. Instead of 9 pixels down, use the height of the seqtime and the height of a character.

12.65.2.7 void seq64::seqtime::change_horz ( ) [private]

12.65.2.8 void seq64::seqtime::update_sizes ( ) [private]

12.65.2.9 bool seq64::seqtime::idle_progress ( ) [inline], [private]

12.65.2.10 void seq64::seqtime::on_realize ( ) [private]

Call the base-class version of this function first. Then addition resources are allocated.

12.65.2.11 bool seq64::seqtime::on_expose_event (GdkEventExpose * *a_ev*) [private]

12.65.2.12 void seq64::seqtime::on_size_allocate (Gtk::Allocation & *a*) [private]

12.65.2.13 bool seq64::seqtime::on_button_press_event (GdkEventButton *) [inline], [private]

Simply returns false.

12.65.2.14 bool seq64::seqtime::on_button_release_event (GdkEventButton *) [inline], [private]

Simply returns false.

12.65.3 Field Documentation

12.65.3.1 sequence& seq64::seqtime::m_seq [private]

12.65.3.2 int seq64::seqtime::m_scroll_offset_ticks [private]

12.65.3.3 int seq64::seqtime::m_scroll_offset_x [private]

12.65.3.4 int seq64::seqtime::m_zoom [private]

12.65.3.5 int seq64::seqtime::m_ppqn [private]

12.66 seq64::sequence Class Reference

The sequence class is firstly a receptable for a single track of MIDI data read from a MIDI file or edited into a pattern.

Public Types

Public Member Functions

- sequence (int ppqn=SEQ64_USE_DEFAULT_PPQN)

  Principal constructor.
- ~sequence ()

  A rote destructor.
- void partial_assign (const sequence &rhs)

  A cut-down version of principal assignment operator.
- event_list & events ()

  'Getter' function for member m_events
- const event_list & events () const

  'Getter' function for member m_events
- bool any_selected_notes () const

  'Getter' function for member m_events.any_selected_notes()
- triggers::List & triggerlist ()

  'Getter' function for member m_triggers
- int number () const

  'Getter' function for member m_seq_number
- void number (int seqnum)

  'Setter' function for member m_seq_number This setter will set the sequence number only if it has not already been set.
- int event_count () const

  Returns the number of events stored in m_events.
- void push_undo ()

  Pushes the event-list into the undo-list.
- void pop_undo ()

  If there are items on the undo list, this function pushes the event-list into the redo-list, puts the top of the undo-list into the event-list, pops from the undo-list, calls verify_and_link(), and then calls unselect.
- void pop_redo ()

  If there are items on the redo list, this function pushes the event-list into the undo-list, puts the top of the redo-list into the event-list, pops from the redo-list, calls verify_and_link(), and then calls unselect.
- void push_trigger_undo ()

  Calls triggers::push_undo() with locking.
- void pop_trigger_undo ()

  Calls triggers::pop_undo() with locking.
- void set_name (const std::string &name)

  Sets the sequence name member, m_name.
- void set_name (char *name)

  Sets the sequence name member, m_name.
- void set_measures (int lengthmeasures)
- int get_measures ()
- int get_ppqn () const

  'Getter' function for member m_ppqn Provided as a convenience for the editable_events class.
- void set_beats_per_bar (int beatspermeasure)

  'Setter' function for member m_time_beats_per_measure
- int get_beats_per_bar () const

  'Getter' function for member m_time_beats_per_measure
- void set_beat_width (int beatwidth)

  'Setter' function for member m_time_beat_width

- int get_beat_width () const

  'Getter' function for member m_time_beat_width
- void clocks_per_metronome (int cpm)

  'Setter' function for member m_clocks_per_metronome
- int clocks_per_metronome () const

  'Getter' function for member m_clocks_per_metronome
- void set_32nds_per_quarter (int tpq)

  'Setter' function for member m_32nds_per_quarter
- int get_32nds_per_quarter () const

  'Getter' function for member m_32nds_per_quarter
- void us_per_quarter_note (int upqn)

  'Setter' function for member m_us_per_quarter_note
- int us_per_quarter_note () const

  'Getter' function for member m_us_per_quarter_note
- void set_rec_vol (int rec_vol)

  'Setter' function for member m_rec_vol
- void set_song_mute (bool mute)

  'Setter' function for member m_song_mute This function also calls set_dirty_mp() to make sure that the perfnames panel is updated to show the new mute status of the sequence.
- void toggle_song_mute ()

  'Setter' function for member m_song_mute This function toogles the song muting status.
- bool get_song_mute () const

  'Getter' function for member m_song_mute
- const char * get_name () const

  'Getter' function for member m_name pointer
- const std::string & name () const

  'Getter' function for member m_name
- void set_editing (bool edit)

  'Setter' function for member m_editing
- bool get_editing () const

  'Getter' function for member m_editing
- void set_raise (bool edit)

  'Setter' function for member m_raise
- bool get_raise (void) const

  'Getter' function for member m_raise
- void set_length (midipulse len, bool adjust_triggers=true)

  Sets the length (m_length) and adjusts triggers for it, if desired.
- midipulse get_length () const

  'Getter' function for member m_length
- midipulse get_last_tick ()

  Returns the last tick played, and is used by the editor's idle function.
- void set_last_tick (midipulse tick)

  'Setter' function for member m_last_tick This function used to be called "set_orig_tick()", now renamed to match up with get_last_tick().
- midipulse mod_last_tick ()

  Some MIDI file errors and other things can lead to an m_length of 0, which causes arithmetic errors when m_last_tick is modded against it.
- void set_playing (bool)

  Sets the playing state of this sequence.
- bool get_playing () const

  'Getter' function for member m_playing

- void toggle_playing ()

  Toggles the playing status of this sequence.
- void toggle_queued ()

  'Setter' function for member m_queued and m_queued_tick Toggles the queued flag and sets the dirty-mp flag.
- void off_queued ()

  'Setter' function for member m_queued Turns off (resets) the queued flag and sets the dirty-mp flag.
- void on_queued ()

  'Setter' function for member m_queued Turns on (sets) the queued flag and sets the dirty-mp flag.
- bool get_queued () const

  'Getter' function for member m_queued
- midipulse get_queued_tick () const

  'Getter' function for member m_queued_tick
- bool check_queued_tick (midipulse tick) const

  Helper function for perform.
- void set_recording (bool)

  'Setter' function for member m_recording and m_notes_on
- bool get_recording () const

  'Getter' function for member m_recording
- void set_snap_tick (int st)

  'Setter' function for member m_snap_tick
- void set_quantized_rec (bool qr)

  'Setter' function for member m_quantized_rec
- bool get_quantized_rec () const

  'Getter' function for member m_quantized_rec
- void set_thru (bool)

  'Setter' function for member m_thru
- bool get_thru () const

  'Getter' function for member m_thru
- bool is_dirty_main ()

  Returns the value of the dirty main flag, and sets that flag to false (i.e.
- bool is_dirty_edit ()

  Returns the value of the dirty edit flag, and sets that flag to false.
- bool is_dirty_perf ()

  Returns the value of the dirty performance flag, and sets that flag to false.
- bool is_dirty_names ()

  Returns the value of the dirty names (heh heh) flag, and sets that flag to false.
- void set_dirty_mp ()

  Sets the dirty flags for names, main, and performance.
- void set_dirty ()

  Call set_dirty_mp() and then sets the dirty flag for editing.
- midibyte get_midi_channel () const

  'Getter' function for member m_midi_channel
- bool is_smf_0 () const

  Returns true if this sequence is an SMF 0 sequence.
- void set_midi_channel (midibyte ch)

  Sets the m_midi_channel number.
- void print () const

  Prints a list of the currently-held events.
- void print_triggers () const

  Prints a list of the currently-held triggers.
- void play (midipulse tick, bool playback_mode)

The play() function dumps notes starting from the given tick, and it pre-buffers ahead.

- bool add_event (const event &er)

  Adds an event to the internal event list in a sorted manner.
- void add_trigger (midipulse tick, midipulse len, midipulse offset=0, bool adjust_offset=true)

  Adds a trigger.
- void split_trigger (midipulse tick)

  Splits a trigger.
- void grow_trigger (midipulse tick_from, midipulse tick_to, midipulse len)

  Grows a trigger.
- void del_trigger (midipulse tick)

  Deletes a trigger, that brackets the given tick, from the trigger-list.
- bool get_trigger_state (midipulse tick)

  Checks the list of triggers against the given tick.
- bool select_trigger (midipulse tick)

  Checks the list of triggers against the given tick.
- bool unselect_triggers ()

  Unselects all triggers.
- bool intersect_triggers (midipulse position, midipulse &start, midipulse &ender)

  This function examines each trigger in the trigger list.
- bool intersect_notes (midipulse position, midipulse position_note, midipulse &start, midipulse &ender, int &note)

  This function examines each note in the event list.
- bool intersect_events (midipulse posstart, midipulse posend, midibyte status, midipulse &start)

  This function examines each non-note event in the event list.
- void del_selected_trigger ()

  Deletes the first selected trigger that is found.
- void cut_selected_trigger ()

  Copies and deletes the first selected trigger that is found.
- void copy_selected_trigger ()

  Copies the first selected trigger that is found.
- void paste_trigger ()

  If there is a copied trigger, then this function grabs it from the trigger clipboard and adds it.
- bool move_selected_triggers_to (midipulse tick, bool adjust_offset, int which=2)

  Moves selected triggers as per the given parameters.
- midipulse selected_trigger_start ()

  Gets the last-selected trigger's start tick.
- midipulse selected_trigger_end ()

  Gets the selected trigger's end tick.
- midipulse get_max_trigger ()

  Get the ending value of the last trigger in the trigger-list.
- void move_triggers (midipulse start_tick, midipulse distance, bool direction)

  Moves triggers in the trigger-list.
- void copy_triggers (midipulse start_tick, midipulse distance)

  Copies triggers to another location.
- void clear_triggers ()

  Clears the whole list of triggers.
- midipulse get_trigger_offset () const

  'Getter' function for member m_trigger_offset
- void set_midi_bus (char mb)

  Sets the midibus number to dump to.
- char get_midi_bus () const

'Getter' function for member m_bus

- void set_master_midi_bus (mastermidibus *mmb)

  'Setter' function for member m_masterbus Do we need to call set_dirty_mp() here?
- int select_note_events (midipulse tick_s, int note_h, midipulse tick_f, int note_l, select_action_e action)

  This function selects events in range of tick start, note high, tick end, and note low.
- int select_events (midipulse tick_s, midipulse tick_f, midibyte status, midibyte cc, select_action_e action)

  Select all events in the given range, and returns the number selected.
- int select_events (midibyte status, midibyte cc, bool inverse=false)

  Select all events with the given status, and returns the number selected.
- void select_all_notes (bool inverse=false)
- int get_num_selected_notes () const

  Counts the selected notes in the event list.
- int get_num_selected_events (midibyte status, midibyte cc) const

  Counts the selected events, with the given status, in the event list.
- void select_all ()

  Selects all events, unconditionally.
- void copy_selected ()

  Copies the selected events.
- void cut_selected (bool copyevents=true)

  Cuts the selected events.
- void paste_selected (midipulse tick, int note)

  Pastes the selected notes (and only note events) at the given tick and the given note value.
- void get_selected_box (midipulse &tick_s, int &note_h, midipulse &tick_f, int &note_l)

  Returns the 'box' of the selected items.
- void get_clipboard_box (midipulse &tick_s, int &note_h, midipulse &tick_f, int &note_l)

  Returns the 'box' of the clipboard items.
- midipulse adjust_timestamp (midipulse t, bool isnoteoff=false)

  A new function to consolidate the adjustment of timestamps in a pattern.
- midipulse clip_timestamp (midipulse ontime, midipulse offtime)

  A new function to consolidate the growth/shrinkage of timestamps in a pattern.
- void move_selected_notes (midipulse deltatick, int deltanote)

  Removes and adds selected notes in position.
- void add_note (midipulse tick, midipulse len, int note, bool paint=false)

  Adds a note of a given length and note value, at a given tick location.
- void add_event (midipulse tick, midibyte status, midibyte d0, midibyte d1, bool paint=false)

  Adds a event of a given status value and data values, at a given tick location.
- void stream_event (event &ev)

  Streams the given event.
- bool change_event_data_range (midipulse tick_s, midipulse tick_f, midibyte status, midibyte cc, int d_s, int d_f)

  Changes the event data range.
- void increment_selected (midibyte status, midibyte)

  Increments events the match the given status and control values.
- void decrement_selected (midibyte status, midibyte)

  Decrements events the match the given status and control values.
- void grow_selected (midipulse deltatick)

  The original description was "Moves note off event." But this also gets called when simply selecting a second note via a ctrl-left-click, even in seq24.
- void stretch_selected (midipulse deltatick)

  Performs a stretch operation on the selected events.
- bool remove_marked ()

Removes marked events.

- void mark_selected ()

  Marks the selected events.

- void remove_selected ()

  Removes selected events.

- void unpaint_all ()

  Unpaints all events in the event-list.

- void unselect ()

  Deselects all events, unconditionally.

- void verify_and_link ()

  This function verifies state: all note-ons have a note-off, and it links note-offs with their note-ons.

- void link_new ()

  Links a new event.

- void zero_markers ()

  Resets everything to zero.

- void play_note_on (int note)

  Plays a note from the piano roll on the main bus on the master MIDI buss.

- void play_note_off (int note)

  Turns off a note from the piano roll on the main bus on the master MIDI buss.

- void off_playing_notes ()

  Sends a note-off event for all active notes.

- void pause ()

  A pause version of reset().

- void reset (bool live_mode)

  Provides a helper function simplify and speed up perform::reset_sequences().

- void reset_draw_marker ()

  This refreshes the play marker to the last tick.

- void reset_draw_trigger_marker ()

  Sets the draw-trigger iterator to the beginning of the trigger list.

- draw_type get_next_note_event (midipulse *tick_s, midipulse *tick_f, int *note, bool *selected, int *velocity)

  Each call to seqdata() fills the passed references with a events elements, and returns true.

- bool get_minmax_note_events (int &lowest, int &highest)

  A new function provided so that we can find the minimum and maximum notes with only one (not two) traversal of the event list.

- bool get_next_event (midibyte status, midibyte cc, midipulse *tick, midibyte *d0, midibyte *d1, bool *selected)

  Get the next event in the event list that matches the given status and control character.

- bool get_next_event (midibyte *status, midibyte *cc)

  Get the next event in the event list.

- bool get_next_trigger (midipulse *tick_on, midipulse *tick_off, bool *selected, midipulse *tick_offset)

  Get the next trigger in the trigger list, and set the parameters based on that trigger.

- void fill_container (midi_container &c, int tracknumber)

  This function fills the given MIDI container with MIDI data from the current sequence, preparatory to writing it to a file.

- void quantize_events (midibyte status, midibyte cc, midipulse snap_tick, int divide, bool linked=false)

  Grabs the specified events, puts them into a list, quantizes them against the snap ticks, and merges them in to the event container.

- void push_quantize (midibyte status, midibyte cc, midipulse snap_tick, int divide, bool linked=false)

  A new convenience function.

- void transpose_notes (int steps, int scale)

  Transposes notes by the given steps, in accordance with the given scale.

- midibyte musical_key () const

  'Getter' function for member m_musical_key

- void musical_key (int key)

  'Setter' function for member m_musical_key
- midibyte musical_scale () const

  'Getter' function for member m_musical_scale
- void musical_scale (int scale)

  'Setter' function for member m_musical_scale
- int background_sequence () const

  'Getter' function for member m_background_sequence
- void background_sequence (int bs)

  'Setter' function for member m_background_sequence Only partial validation at present, we do not want the upper limit to be hard-wired at this time.
- void show_events () const

  A member function to dump a summary of events stored in the event-list of a sequence.
- void copy_events (const event_list &newevents)

  Copies an external container of events into the current container, effectively replacing all of its events.
- midipulse note_off_margin () const

  'Getter' function for member m_note_length

Private Types

- typedef std::stack< event_list > EventStack

  Provides a stack of event-lists for use with the undo and redo facility.

Private Member Functions

- sequence & operator= (const sequence &rhs)
- void set_parent (perform *p)

  'Setter' function for member m_parent Sets the "parent" of this sequence, so that it can get some extra information about the performance.
- void put_event_on_bus (event &ev)

  Takes an event that this sequence is holding, and places it on the MIDI buss.
- void set_trigger_offset (midipulse trigger_offset)

  Sets m_trigger_offset and wraps it to m_length.
- void split_trigger (trigger &trig, midipulse splittick)

  Splits the trigger given by the parameter into two triggers.
- void adjust_trigger_offsets_to_length (midipulse newlen)

  Adjusts trigger offsets to the length specified for all triggers, and undo triggers.
- midipulse adjust_offset (midipulse offset)
- void remove (event_list::iterator i)

  A helper function, which does not lock/unlock, so it is unsafe to call without supplying an iterator from the event-list.
- void remove (event &e)

  A helper function, which does not lock/unlock, so it is unsafe to call without supplying an iterator from the event-list.
- void remove_all ()

  Clears all events from the event container.

Private Attributes

- perform * m_parent

  For pause support, we need a way for the sequence to find out if JACK transport is active.
- event_list m_events

  This list holds the current pattern/sequence events.
- triggers m_triggers

  The triggers associated with the sequence, used in the performance/song editor.
- EventStack m_events_undo

  Provides a list of event actions to undo.
- EventStack m_events_redo

  Provides a list of event actions to redo.
- event_list::iterator m_iterator_draw

  An iterator for drawing events.
- midibyte m_midi_channel

  Contains the proper MIDI channel for this sequence.
- midibyte m_bus

  Contains the proper MIDI bus number for this sequence.
- bool m_song_mute

  Provides a flag for the song playback mode muting.
- int m_notes_on

  Provides a member to hold the polyphonic step-edit note counter.
- mastermidibus * m_masterbus

  Provides the master MIDI buss which handles the output of the sequence to the proper buss and MIDI channel.
- int m_playing_notes [SEQ64_MIDI_NOTES_MAX]

  Provides a "map" for Note On events.
- bool m_was_playing

  Indicates if the sequence was playing.
- bool m_playing

  True if sequence playback currently is in progress for this sequence.
- bool m_recording

  True if sequence recording currently is in progress for this sequence.
- bool m_quantized_rec

  True if recoring in quantized mode.
- bool m_thru

  True if recoring in MIDI-through mode.
- bool m_queued

  True if the events are queued.
- bool m_dirty_main

  These flags indicate that the content of the sequence has changed due to recording, editing, performance management, or even (?) a name change.
- bool m_dirty_edit

  Provides the main is-edited flag.
- bool m_dirty_perf

  Provides performance dirty flagflag.
- bool m_dirty_names

  Provides the names dirtiness flag.
- bool m_editing

  Indicates that the sequence is currently being edited.
- bool m_raise

  Used in seqmenu and seqedit.

- std::string m_name

  Provides the name/title for the sequence.
- midipulse m_last_tick

  These members manage where we are in the playing of this sequence, including triggering.
- midipulse m_queued_tick

  Provides the next tick to play?
- midipulse m_trigger_offset

  Provides the trigger offset.
- const int m_maxbeats

  This constant provides the scaling used to calculate the time position in ticks (pulses), based also on the PPQN value.
- int m_ppqn

  Holds the PPQN value for this sequence, so that we don't have to rely on a global constant value.
- int m_seq_number

  A new member so that the sequence number is carried along with the sequence.
- midipulse m_length

  Holds the length of the sequence in pulses (ticks).
- midipulse m_snap_tick

  The size of snap in units of pulses (ticks).
- int m_time_beats_per_measure

  Provides the number of beats per bar used in this sequence.
- int m_time_beat_width

  Provides with width of a beat.
- int m_clocks_per_metronome

  Augments the beats/bar and beat-width with the additional values included in a Time Signature meta event.
- int m_32nds_per_quarter

  Augments the beats/bar and beat-width with the additional values included in a Time Signature meta event.
- int m_us_per_quarter_note

  Augments the beats/bar and beat-width with the additional values included in a Tempo meta event.
- int m_rec_vol

  The volume to be used when recording.
- midibyte m_musical_key

  Holds a copy of the musical key for this sequence, which we now support writing to this sequence.
- midibyte m_musical_scale

  Holds a copy of the musical scale for this sequence, which we now support writing to this sequence.
- int m_background_sequence

  Holds a copy of the background sequence number for this sequence, which we now support writing to this sequence.
- mutex m_mutex

  Provides locking for the sequence.
- const midipulse m_note_off_margin

  Provides the number of ticks to shave off of the end of painted notes.

Static Private Attributes

- static event_list m_events_clipboard

  A static clipboard for holding pattern/sequence events.

Friends

- class perform
- class triggers

12.66.1 Detailed Description

More members than you can shake a stick at.

12.66.2 Member Typedef Documentation

12.66.2.1 typedef std::stack<event_list> seq64::sequence::EventStack [private]

12.66.3 Member Enumeration Documentation

12.66.3.1 enum seq64::sequence::select_action_e

Se the select_note_events() and select_events() functions.

Enumerator

e_select To select an event.

e_select_one To select a single event.

e_is_selected The events are selected.

e_would_select The events would be selected.

e_deselect To deselect the event under the cursor.

e_toggle_selection To toggle the selection of the event under the cursor.

e_remove_one To remove one note under the cursor.

12.66.4 Constructor & Destructor Documentation

12.66.4.1 seq64::sequence::sequence (int *ppqn* = SEQ64_USE_DEFAULT_PPQN)

Parameters

ppqn	Provides the PPQN parameter to perhaps alter the default PPQN value of this sequence.

12.66.4.2 seq64::sequence::~sequence ( )

12.66.5 Member Function Documentation

12.66.5.1 sequence& seq64::sequence::operator= (const sequence & *rhs*) [private]

12.66.5.2 void seq64::sequence::partial_assign (const sequence & *rhs*)

We're replacing that incomplete function (many members are not assigned) with the more accurately-named partial_assign() function.

It did not assign them all, so we created this partial_assign() function to do this work, and replaced operator =() with this function in client code.

Threadsafe

Parameters

rhs	Provides the source of the new member values.

12.66.5.3 event_list& seq64::sequence::events ( ) [inline]

12.66.5.4 const event_list& seq64::sequence::events ( ) const [inline]

12.66.5.5 bool seq64::sequence::any_selected_notes ( ) const [inline]

12.66.5.6 triggers::List& seq64::sequence::triggerlist ( ) [inline]

12.66.5.7 int seq64::sequence::number ( ) const [inline]

12.66.5.8 void seq64::sequence::number (int *seqnum*) [inline]

12.66.5.9 int seq64::sequence::event_count ( ) const

Note that only playable events are counted in a sequence. If a sequence class function provides a mutex, call m_events.count() instead.

Threadsafe

Returns

Returns m_events.count().

12.66.5.10 void seq64::sequence::push_undo ( )

Threadsafe

12.66.5.11 void seq64::sequence::pop_undo ( )

Threadsafe

12.66.5.12 void seq64::sequence::pop_redo ( )

Threadsafe

12.66.5.13 void seq64::sequence::push_trigger_undo ( )

Threadsafe

12.66.5.14 void seq64::sequence::pop_trigger_undo ( )

12.66.5.15 void seq64::sequence::set_name (const std::string & *name*)

12.66.5.16 void seq64::sequence::set_name (char * *name*)

12.66.5.17 void seq64::sequence::set_measures (int *lengthmeasures*)

12.66.5.18 int seq64::sequence::get_measures ( )

12.66.5.19 int seq64::sequence::get_ppqn ( ) const [inline]

12.66.5.20 void seq64::sequence::set_beats_per_bar (int *beatspermeasure*)

Threadsafe

Parameters

beatspermeasure	The new setting of the beats-per-bar value.

12.66.5.21 int seq64::sequence::get_beats_per_bar ( ) const [inline]

12.66.5.22 void seq64::sequence::set_beat_width (int *beatwidth*)

Threadsafe

Parameters

beatwidth	The new setting of the beat width value.

12.66.5.23 int seq64::sequence::get_beat_width ( ) const [inline]

Threadsafe

12.66.5.24 void seq64::sequence::clocks_per_metronome (int *cpm*) [inline]

12.66.5.25 int seq64::sequence::clocks_per_metronome ( ) const [inline]

12.66.5.26 void seq64::sequence::set_32nds_per_quarter (int *tpq*) [inline]

12.66.5.27 int seq64::sequence::get_32nds_per_quarter ( ) const [inline]

12.66.5.28 void seq64::sequence::us_per_quarter_note (int *upqn*) [inline]

12.66.5.29 int seq64::sequence::us_per_quarter_note ( ) const [inline]

12.66.5.30 void seq64::sequence::set_rec_vol (int *recvol*)

Threadsafe

Parameters

recvol	The new setting of the recording volume setting.

12.66.5.31 void seq64::sequence::set_song_mute (bool *mute*) [inline]

12.66.5.32 void seq64::sequence::toggle_song_mute ( ) [inline]

12.66.5.33 bool seq64::sequence::get_song_mute ( ) const [inline]

12.66.5.34 const char* seq64::sequence::get_name ( ) const [inline]

Deprecated

12.66.5.35 const std::string& seq64::sequence::name ( ) const [inline]

12.66.5.36 void seq64::sequence::set_editing (bool *edit*) [inline]

12.66.5.37 bool seq64::sequence::get_editing ( ) const [inline]

12.66.5.38 void seq64::sequence::set_raise (bool *edit*) [inline]

12.66.5.39 bool seq64::sequence::get_raise (void) const [inline]

12.66.5.40 void seq64::sequence::set_length (midipulse *len*, bool *adjust_triggers* = true)

This function is called in seqedit::apply_length(), when the user selects a sequence length in measures. That function calculates the length in ticks:

```
    L = M x B x 4 x P / W
        L == length (ticks or pulses)
        M == number of measures
        B == beats per measure
        P == pulses per quarter-note
        W == beat width in beats per measure


For our "b4uacuse" MIDI file, M can be about 100 measures, B is 4,
P can be 192 (but we want to support higher values), and W is 4.
So L = 100 * 4 * 4 * 192 / 4 = 76800 ticks.  Seems small.
```

Threadsafe

12.66.5.41 midipulse seq64::sequence::get_length ( ) const [inline]

12.66.5.42 midipulse seq64::sequence::get_last_tick ( )

If m_length is 0, this function returns m_last_tick - m_trigger_offset, to avoid an arithmetic exception. Should we return 0 instead?

Note that seqroll calls this function to help get the location of the progress bar. What does perfedit do?

12.66.5.43 void seq64::sequence::set_last_tick (midipulse *tick*)

Threadsafe

12.66.5.44 midipulse seq64::sequence::mod_last_tick ( ) [inline]

This function replaces the "m_last_tick % m_length", returning m_last_tick if m_length is 0 or 1.

12.66.5.45 void seq64::sequence::set_playing (bool *p*)

When playing, and the sequencer is running, notes get dumped to the ALSA buffers.

Parameters

p	Provides the playing status to set. True means to turn on the playing, false means to turn it off, and turn off any notes still playing.

12.66.5.46 bool seq64::sequence::get_playing ( ) const [inline]

12.66.5.47 void seq64::sequence::toggle_playing ( ) [inline]

How exactly does this differ from toggling the mute status?

12.66.5.48 void seq64::sequence::toggle_queued ( )

Also calculates the queued tick based on m_last_tick.

Threadsafe

12.66.5.49 void seq64::sequence::off_queued ( )

Do we need to set m_queued_tick as in toggle_queued()? Currently not used.

Threadsafe

12.66.5.50 void seq64::sequence::on_queued ( )

Do we need to set m_queued_tick as in toggle_queued()? Currently not used.

Threadsafe

12.66.5.51 bool seq64::sequence::get_queued ( ) const [inline]

12.66.5.52 midipulse seq64::sequence::get_queued_tick ( ) const [inline]

12.66.5.53 bool seq64::sequence::check_queued_tick (midipulse *tick*) const [inline]

12.66.5.54 void seq64::sequence::set_recording (bool *r*)

Threadsafe

12.66.5.55 bool seq64::sequence::get_recording ( ) const [inline]

12.66.5.56 void seq64::sequence::set_snap_tick (int *st*)

Threadsafe

12.66.5.57 void seq64::sequence::set_quantized_rec (bool *qr*)

Threadsafe

12.66.5.58 bool seq64::sequence::get_quantized_rec ( ) const [inline]

12.66.5.59 void seq64::sequence::set_thru (bool *r*)

Threadsafe

12.66.5.60 bool seq64::sequence::get_thru ( ) const [inline]

12.66.5.61 bool seq64::sequence::is_dirty_main ( )

resets it). This flag signals that a redraw is needed from recording.

Threadsafe

Returns

Returns the dirty status.

12.66.5.62 bool seq64::sequence::is_dirty_edit ( )

The m_dirty_edit flag is set by the function set_dirty().

Threadsafe

Returns

Returns the dirty status.

12.66.5.63 bool seq64::sequence::is_dirty_perf ( )

Threadsafe

Returns

Returns the dirty status.

12.66.5.64 bool seq64::sequence::is_dirty_names ( )

Not sure that we need to lock a boolean on modern processors.

Threadsafe

Returns

Returns the dirty status.

12.66.5.65 void seq64::sequence::set_dirty_mp ( )

These flags are meant for causing user-interface refreshes, not for performance modification.

m_dirty_names is set to false in is_dirty_names(); m_dirty_names is set to false in is_dirty_main(); m_dirty_names is set to false in is_dirty_perf().

Not threadsafe

12.66.5.66 void seq64::sequence::set_dirty ( )

Threadsafe

12.66.5.67 midibyte seq64::sequence::get_midi_channel ( ) const [inline]

12.66.5.68 bool seq64::sequence::is_smf_0 ( ) const [inline]

12.66.5.69 void seq64::sequence::set_midi_channel (midibyte *ch*)

Threadsafe

12.66.5.70 void seq64::sequence::print ( ) const

Not threadsafe

12.66.5.71 void seq64::sequence::print_triggers ( ) const

Not threadsafe

12.66.5.72 void seq64::sequence::play (midipulse *tick,* bool *playback_mode*)

This function is called by the sequencer thread, performance. The tick comes in as global tick.

It turns the sequence off after we play in this frame.

Note

With pause support, the progress bar for the pattern/sequence editor does what we want: pause with the pause button, and rewind with the stop button. Works with JACK, with issues, but we'd like to have the stop button do a rewind in JACK, too.

Parameters

tick	Provides the current end-tick value.
playback_mode	Provides how playback is managed. True indicates that it is performance/song-editor playback, controlled by the set of patterns and triggers set up in that editor, and saved with the song in seq24 format. False indicates that the playback is controlled by the main windows, in live mode.

Threadsafe

12.66.5.73 bool seq64::sequence::add_event (const event & *er*)

Then it reset the draw-marker and sets the dirty flag.

Currently, when reading a MIDI file [see the midifile::parse() function], only the main events (notes, after-touch, pitch, program changes, etc.) are added with this function. So, we can rely on reading only playable events into a sequence. Well, actually, certain meta-events are also read, to obtain channel, buss, and more settings. Also read for a sequence, if the global-sequence flag is not set, are the new key, scale, and background sequence parameters.

This module (sequencer) adds all of those events as well, but it can surely add other events. We should assume that any events added by sequencer are playable/usable.

Here, we could ignore events not on the sequence's channel, as an option. We have to be careful because this function can be used in painting events.

Threadsafe

Warning

This pushing (and, in writing the MIDI file, the popping), causes events with identical timestamps to be written in reverse order. Doesn't affect functionality, but it's puzzling until one understands what is happening. Actually, this is true only in Seq24, we've fixed that behavior for Sequencer64.

Parameters

er	Provide a reference to the event to be added; the event is copied into the events container.

Returns

Returns true if the event was added.

12.66.5.74 void seq64::sequence::add_trigger (midipulse *tick*, midipulse *len*, midipulse *offset* = `0`, bool *fixoffset* = `true`)

A pass-through function that calls triggers::add(). See that function for more details.

Threadsafe

Parameters

tick	The time destination of the trigger.
len	The duration of the trigger.
offset	The performance offset of the trigger.
fixoffset	If true, adjust the offset.

12.66.5.75 void seq64::sequence::split_trigger (midipulse *splittick*)

This is the public overload of split_trigger.

Threadsafe

Parameters

splittick	The time location of the split.

12.66.5.76 void seq64::sequence::grow_trigger (midipulse *tickfrom*, midipulse *tickto*, midipulse *len*)

See triggers::grow() for more information.

Parameters

tickfrom	The desired from-value back which to expand the trigger, if necessary.
tickto	The desired to-value towards which to expand the trigger, if necessary.
len	The additional length to append to tickto for the check.

Threadsafe

12.66.5.77 void seq64::sequence::del_trigger (midipulse *tick*)

See triggers::remove().

Threadsafe

Parameters

tick	Provides the tick to be used for finding the trigger to be erased.

12.66.5.78 bool seq64::sequence::get_trigger_state (midipulse *tick*)

If any trigger is found to bracket that tick, then true is returned.

Parameters

tick	Provides the tick of interest.

Returns

Returns true if a trigger is found that brackets the given tick.

12.66.5.79 bool seq64::sequence::select_trigger (midipulse *tick*)

If any trigger is found to bracket that tick, then true is returned, and the trigger is marked as selected.

Parameters

tick	Provides the tick of interest.

Returns

Returns true if a trigger is found that brackets the given tick; this is the return value of m_triggers.select().

12.66.5.80 bool seq64::sequence::unselect_triggers ( )

Returns

Returns the m_triggers.unselect() return value.

12.66.5.81 bool seq64::sequence::intersect_triggers (midipulse *position,* midipulse & *start,* midipulse & *ender*)

If the given position is between the current trigger's tick-start and tick-end values, the these values are copied to the start and end parameters, respectively, and then we exit. See triggers::intersect().

Threadsafe

Parameters

position	The position to examine.
start	The destination for the starting tick of the matching trigger.
ender	The destination for the ending tick of the matching trigger.

Returns

Returns true if a trigger was found whose start/end ticks contained the position. Otherwise, false is returned, and the start and end return parameters should not be used.

12.66.5.82 bool seq64::sequence::intersect_notes (midipulse *position,* midipulse *position_note,* midipulse & *start,* midipulse & *ender,* int & *note*)

If the given position is between the current notes on and off time values, values, the these values are copied to the start and end parameters, respectively, the note value is copied to the note parameter, and then we exit.

Threadsafe

Parameters

	position	The position to examine.
	position_note	I think this is the note value we might be looking for ???
out	*start*	The destination for the starting timestamp of the matching note.
out	*ender*	The destination for the ending timestamp of the matching note.
out	*note*	The destination for the note of the matching event. Why is this an int value???

Returns

Returns true if a event was found whose start/end ticks contained the position. Otherwise, false is returned, and the start and end return parameters should not be used.

12.66.5.83 bool seq64::sequence::intersect_events (midipulse *posstart,* midipulse *posend,* midibyte *status,* midipulse & *start*)

If the given position is between the current notes's timestamp-start and timestamp-end values, the these values are copied to the posstart and posend parameters, respectively, and then we exit.

Threadsafe

Parameters

posstart	The starting position to examine.
posend	The ending position to examine.
status	The desired status value.
start	The destination for the starting timestamp of the matching trigger.

Returns

Returns true if a event was found whose start/end timestamps contained the position. Otherwise, false is returned, and the start and end return parameters should not be used.

12.66.5.84 void seq64::sequence::del_selected_trigger ( )

12.66.5.85 void seq64::sequence::cut_selected_trigger ( )

12.66.5.86 void seq64::sequence::copy_selected_trigger ( )

12.66.5.87 void seq64::sequence::paste_trigger ( )

Why isn't this protected by a mutex? We will enable this if anything bad happens, such as a deadlock, or corruption, that we can prove happens here.

12.66.5.88 bool seq64::sequence::move_selected_triggers_to (midipulse *tick*, bool *adjustoffset*, int *which* = 2)

```
          min_tick][0                 1][max_tick
                        2

The \a which parameter has three possible values:

-#  If we are moving the 0, use first as offset.
-#  If we are moving the 1, use the last as the offset.
-#  If we are moving both (2), use first as offset.
```

Threadsafe

Parameters

tick	The tick at which the trigger starts.
adjustoffset	Set to true if the offset is to be adjusted.
which	Selects which movement will be done, as discussed above.

Returns

Returns the value of triggers::move_selected(), which indicate that the movement could be made. Used in Seq24PerfInput::handle_motion_key().

12.66.5.89 midipulse seq64::sequence::selected_trigger_start ( )

Threadsafe

Returns

Returns the tick_start() value of the last-selected trigger. If no triggers are selected, then -1 is returned.

12.66.5.90 midipulse seq64::sequence::selected_trigger_end ( )

Threadsafe

Returns

Returns the tick_end() value of the last-selected trigger. If no triggers are selected, then -1 is returned.

12.66.5.91 midipulse seq64::sequence::get_max_trigger ( )

Threadsafe

Returns

Returns the maximum trigger value.

12.66.5.92 void seq64::sequence::move_triggers (midipulse *starttick,* midipulse *distance,* bool *direction*)

Note the dependence on the m_length member being kept in sync with the parent's value of m_length.

Threadsafe

Parameters

starttick	The current location of the triggers.
distance	The distance away from the current location to which to move the triggers.
direction	If true, the triggers are moved forward. If false, the triggers are moved backward.

12.66.5.93 void seq64::sequence::copy_triggers (midipulse *starttick,* midipulse *distance*)

Threadsafe

Parameters

starttick	The current location of the triggers.
distance	The distance away from the current location to which to copy the triggers.

12.66.5.94 void seq64::sequence::clear_triggers ( )

Threadsafe

12.66.5.95 midipulse seq64::sequence::get_trigger_offset ( ) const [inline]

12.66.5.96 void seq64::sequence::set_midi_bus (char *mb*)

Threadsafe

12.66.5.97 char seq64::sequence::get_midi_bus ( ) const [inline]

12.66.5.98 void seq64::sequence::set_master_midi_bus (mastermidibus * *mmb*)

Threadsafe

Parameters

mmb	Provides a pointer to the master MIDI buss for this sequence. This should be a reference, but isn't, nor is it checked.

12.66.5.99 int seq64::sequence::select_note_events (midipulse *tick_s,* int *note_h,* midipulse *tick_f,* int *note_l,* select_action_e *action*)

Returns the number selected.

Threadsafe

Parameters

tick_s	The start time of the selection.
note_h	The high note of the selection.
tick_f	The finish time of the selection.
note_l	The low note of the selection.
action	The action to perform, one of e_select, e_select_one, e_is_selected, e_would_select, e_deselect, e_toggle_selection, and e_remove_one.

Returns

Returns the number of events acted on, or 0 if no desired event was found.

12.66.5.100 int seq64::sequence::select_events (midipulse *tick_s,* midipulse *tick_f,* midibyte *status,* midibyte *cc,* select_action_e *action*)

Note that there is also an overloaded version of this function.

Threadsafe

Parameters

tick_s	The start time of the selection.
tick_f	The finish time of the selection.
status	The desired event in the selection.
cc	The desired control-change in the selection, if the event is a control-change.
action	The desired selection action.

Returns

Returns the number of events selected.

12.66.5.101 int seq64::sequence::select_events (midibyte *status*, midibyte *cc*, bool *inverse* = `false`)

Note that there is also an overloaded version of this function.

Threadsafe

Warning

This used to be a void function, so it just returns 0 for now.

Parameters

status	Provides the status value to be selected.
cc	If the status is EVENT_CONTROL_CHANGE, then data byte 0 must match this value.
inverse	If true, invert the selection.

Returns

Always returns 0.

12.66.5.102 void seq64::sequence::select_all_notes (bool *inverse* = `false`) [inline]

12.66.5.103 int seq64::sequence::get_num_selected_notes ( ) const

Threadsafe

Returns

Returns m_events.count_selected_notes().

12.66.5.104 int seq64::sequence::get_num_selected_events (midibyte *status*, midibyte *cc*) const

If the event is a control change (CC), then it must also match the given CC value.

Threadsafe

Parameters

status	The desired kind of event to count.
cc	The desired control-change to count, if the event is a control-change.

Returns

Returns m_events.count_selected_events().

12.66.5.105 void seq64::sequence::select_all ( )

Threadsafe

12.66.5.106 void seq64::sequence::copy_selected ( )

This function also has the danger, discovered by user 0rel, of events being modified after being added to the clipboard. So we add his reconstruction fix here as well. To summarize the steps:

```
-#  Clear the m_events_clipboard.
-#  Add all selected events in this clipboard to the sequence.
-#  Normalize the timestamps of the events in the clip relative to the
    timestamp of the first selected event.  (Is this really needed?)
-#  Reconstruct/reconstitute the m_events_clipboard.
```

This process is a bit easier to manage than erase/insert on events because std::multimap has no erase() function that returns the next valid iterator. Also, we use a local clipboard first, to save on copying. We've enhanced the error-checking, too.

Finally, note that m_events_clipboard is a static member of sequence, so:

```
-#  Copying can be done between sequences.
-#  Access to it needs to be protected by a mutex.
```

Threadsafe

12.66.5.107 void seq64::sequence::cut_selected (bool *copyevents* = `true`)

Pushes onto the undo stack, may copy the events, marks the selected events, and removes them. Now also sets the dirty flag so that the caller doesn't have to. Also raises the modify flag on the parent perform object.

Threadsafe

Parameters

copyevents	If true, copy the selected events before marking and removing them.

12.66.5.108 void seq64::sequence::paste_selected (**midipulse** *tick*, **int** *note*)

Also, we've moved external calls to push_undo() into this function. The caller shouldn't have to do that.

The event_keys used to access/sort the multimap event_list is not updated after changing timestamp/rank of the stored events. Regenerating all key/value pairs before merging them solves this issue, so that the order of events in the sequence will be preserved. This action is not needed for moving or growing events. Nor is it needed if the old std::list implementation of the event container is compiled in. However, it is needed in any operation that modifies the timestamp of an event inside the container:

```
-   copy_selected()
-   paste_selected()
-   quantize_events() TODO TODO TODO!
```

The alternative to reconstructing the map is to erase-and-insert the events modified in the code above, rather than just tweaking their values, which have an effect on sorting for the event-map implementation. However, multimap does not provide an erase() function that returns the next valid iterator, which would complicate this method of operation. So we're inclined to stick with this solution.

There was an issue with copy/pasting a whole sequence. The pasted events did not go to their destination, but overlayed the original events. This bugs also occurred in Seq24 0.9.2. It occurs with the allofarow.mid file when doing Ctrl-A Ctrl-C Ctrl-V Move-Mouse Left-Click. It turns out the original code was checking only the first event to see if it was a Note event. For sequences that started with a Control Change or Program Change (or other non-Note events), the highest note was never modified, and none of the note events were adjusted.

Finally, we only want to transpose note events (i.e. alter m_data[0]), and not other kinds of events. We still need to figure out what to do with aftertouch, though. Currently likely to be covered by the processing of the note that it accompanies.

Threadsafe

Parameters

tick	The time destination for the paste. This represents the "x" coordinate of the upper left corner of the paste-box. It will be converted to an offset, for example pasting every event 48 ticks forward from the original copy.
note	The note/pitch destination for the paste. This represents the "y" coordinate of the upper left corner of the paste-box. It will be converted to an offset, for example pasting every event 7 notes higher than the original copy.

12.66.5.109 void seq64::sequence::get_selected_box (midipulse & *tick_s*, int & *note_h*, midipulse & *tick_f*, int & *note_l*)

Note the common-code betweem this function and get_clipboard_box(). Also note we could return a boolean indicating if the return values were filled in.

Threadsafe

Parameters

out	*tick_s*	Side-effect return reference for the start time.
out	*note_h*	Side-effect return reference for the high note.
out	*tick_f*	Side-effect return reference for the finish time.
out	*note_l*	Side-effect return reference for the low note.

12.66.5.110 void seq64::sequence::get_clipboard_box (midipulse & *tick_s*, int & *note_h*, midipulse & *tick_f*, int & *note_l*)

Note the common-code betweem this function and get_selected_box(). Also note we could return a boolean indicating if the return values were filled in.

Threadsafe

Parameters

out	*tick_s*	Side-effect return reference for the start time.
out	*note_h*	Side-effect return reference for the high note.
out	*tick_f*	Side-effect return reference for the finish time.
out	*note_l*	Side-effect return reference for the low note.

12.66.5.111 midipulse seq64::sequence::adjust_timestamp (midipulse *t*, bool *isnoteoff* = false)

If the timestamp is greater that m_length, we do round robin magic. Taken from similar code in move_selected_notes() and grow_selected(). Be careful using this function.

Parameters

t	Provides the timestamp to be adjusted based on m_length.
isnoteoff	Used for "expanding" the timestamp from 0 to just less than m_length, if necessary. Should be set to true only for Note Off events; it defaults to false, which means to wrap the events around the end of the sequence if necessary, and is used only in movement, not in growth.

Returns

Returns the adjusted timestamp.

12.66.5.112 midipulse seq64::sequence::clip_timestamp (midipulse *ontime*, midipulse *offtime*)

If the new (off) timestamp is less than the on-time, it is clipped to the snap value. If it is greater than the length of the sequence, then it is clipped to the sequence length. No wrap-around.

Parameters

ontime	Provides the original time, which limits the amount of negative adjustment that can be done.
offtime	Provides the timestamp to be adjusted and clipped.

Returns

Returns the adjusted timestamp.

12.66.5.113 void seq64::sequence::move_selected_notes (midipulse *delta_tick*, int *delta_note*)

Also currently moves any other events in the range of the selection.

Also, we've moved external calls to push_undo() into this function. The caller shouldn't have to do that.

Another thing this function does is wrap-around when movement occurs. Any events (except Note Off) that will start just after the END of the pattern will be wrapped around to the beginning of the pattern.

Fixed:

Select all notes in a short pattern that starts at time 0 and has non-note events starting at time 0 (see contrib/midi/allofarow.mid); move them with the right arrow, and move them back with the left arrow; then view in the event editor, and see that the non-Note events have not moved back, and in fact move way too far to the right, actually to near the END marker. We've fixed that in the new adjust_timestamp() function.

This function checks for any marked events in seq24, but now we make sure the event is a Note On or Note Off event before dealing with it. We now handle properly events like Program Change, Control Change, and Pitch Wheel. Remember that Aftertouch is treated like a note, as it has velocity. For non-Notes, event::get_note() returns m_data[0], and we don't want to adjust that.

Parameters

delta_tick	Provides the amount of time to move the selected notes. Note that it also applies to events. Note-Off events are expanded to m_length if their timestamp would be 0. All other events will wrap around to 0.
delta_note	Provides the amount of pitch to move the selected notes. This value is applied only to Note (On and Off) events. Also, if this value would bring a note outside the range of 0 to 127, that note is not changed and the event is not moved.

12.66.5.114 void seq64::sequence::add_note (midipulse *tick*, midipulse *len*, int *note*, bool *paint* = `false`)

It adds a single note-on / note-off pair.

The paint parameter indicates if we care about the painted event, so then the function runs though the events and deletes the painted ones that overlap the ones we want to add.

Also note that push_undo() is not incorporated into this function, for the sake of speed.

Here, we could ignore events not on the sequence's channel, as an option. We have to be careful because this function can be used in painting notes.

Threadsafe

Parameters

tick	The time destination of the new note, in pulses.
len	The duration of the new note, in pulses.
note	The pitch destination of the new note.
paint	If true, repaint the whole set of events, in order to be left with a clean view of the inserted event. The default is false.

12.66.5.115 void seq64::sequence::add_event (midipulse *tick*, midibyte *status*, midibyte *d0*, midibyte *d1*, bool *paint* = `false`)

The paint parameter indicates if we care about the painted event, so then the function runs though the events and deletes the painted ones that overlap the ones we want to add.

Threadsafe

Parameters

tick	The time destination of the event.
status	The type of event to add.
d0	The first data byte for the event.
d1	The second data byte for the event (if needed).
paint	If true, the inserted event is marked for painting.

12.66.5.116 void seq64::sequence::stream_event (event & *ev*)

The event's timestamp is adjusted, if needed. If recording:

```
-   If the pattern is playing, the event is added.
-   If the pattern is playing and quantized record is in force, the
    note's timestamp is altered.
-   If not playing, but the event is a Note On or Note Off, we add it
    and keep track of it.
```

If MIDI Thru is enabled, the event is put on the buss.

Todo Consider adding a feature where event's are rejected if their channel doesn't match that of the sequence. This has been a complaint of some people. Would modify the add_event() and add_note() functions.

Threadsafe

Parameters

ev	Provides the event to stream.

12.66.5.117 bool seq64::sequence::change_event_data_range (midipulse *tick_s*, midipulse *tick_f*, midibyte *status*, midibyte *cc*, int *data_s*, int *data_f*)

Changes only selected events, if any.

Threadsafe

Let t == the current tick value; ts == tick start value; tf == tick finish value; ds = data start value; df == data finish value; d = the new data value. Then

```
             df (t - ts) + ds (tf - t)
        d = -------------------------
                     tf  -   ts
```

```
If this were an interpolation formula it would be:
```

```
                              t -  ts
        d = ds + (df - ds) ---------
                              tf - ts
```

```
Something is not quite right; to be investigated.
```

Parameters

tick_s	Provides the starting tick value.
tick_f	Provides the ending tick value.
status	Provides the event status that is to be changed.
cc	Provides the event control value.
data_s	Provides the starting data value.
data_f	Provides the finishing data value.

Returns

Returns true if the data was changed.

12.66.5.118 void seq64::sequence::increment_selected (midibyte *astat,* midibyte)

The supported statuses are:

```
-   EVENT_NOTE_ON
-   EVENT_NOTE_OFF
-   EVENT_AFTERTOUCH
-   EVENT_CONTROL_CHANGE
-   EVENT_PITCH_WHEEL
-   EVENT_PROGRAM_CHANGE
-   EVENT_CHANNEL_PRESSURE
```

Threadsafe

Parameters

astat	The desired event.

Parameter "acontrol", the desired control-change, is unused. This might be a bug, or at least a missing feature.

12.66.5.119 void seq64::sequence::decrement_selected (midibyte *astat,* midibyte)

The supported statuses are:

- One-byte messages
  - EVENT_PROGRAM_CHANGE
  - EVENT_CHANNEL_PRESSURE
- Two-byte messages
  - EVENT_NOTE_ON
  - EVENT_NOTE_OFF

- EVENT_AFTERTOUCH
- EVENT_CONTROL_CHANGE
- EVENT_PITCH_WHEEL

Threadsafe

Parameters

astat	The desired event.

Parameter "acontrol", the desired control-change, is unused. This might be a bug, or at least a missing feature.

12.66.5.120 void seq64::sequence::grow_selected (midipulse *delta_tick*)

And, though it doesn't move Note Off events, it does reconstruct them.

This function is called when doing a ctrl-left mouse move on the selected notes or when using ctrl-left-arrow or ctrl-right-arrow to shrink or stretch the selected notes. Using the mouse allows pretty much any amount of growth or shrinkage, but use the arrow keys limits the changes to the current snap value.

This function grows/shrinks only Note On events that are marked and linked. If an event is not linked, this function now ignores the event's timestamp, rather than risk a segfault on a null pointer. Compare this function to the stretch_selected() and move_selected_notes() functions.

This function would strip out non-Notes, but now it at least preserves them and moves them, to try to preserve their relative position re the notes.

In any case, we want to mark the original off-event for deletion, otherwise we get duplicate off events, for example in the "Begin/End" pattern in the test.midi file.

This function now tries to prevent pathological growth, such as trying to shrink the notes to zero length or less, or stretch them beyond the length of the sequence. Otherwise we get weird and unexpected results.

Also, we've moved external calls to push_undo() into this function. The caller shouldn't have to do that.

A comment on terminology: The user "selects" notes, while the sequencer "marks" notes. The first thing this function does is mark all the selected notes.

Threadsafe

Parameters

delta_tick	An offset for each linked event's timestamp.

12.66.5.121 void seq64::sequence::stretch_selected (midipulse *delta_tick*)

This should move a note off event, according to old comments, but it doesn't seem to do that. See the grow_↩ selected() function. Rather, it moves any event in the selection.

Also, we've moved external calls to push_undo() into this function. The caller shouldn't have to do that.

Threadsafe

Parameters

delta_tick	Provides the amount of time to stretch the selected notes.

12.66.5.122 bool seq64::sequence::remove_marked ( )

Note how this function forwards the call to m_event.remove_marked().

Threadsafe

Returns

Returns true if at least one event was removed.

12.66.5.123 void seq64::sequence::mark_selected ( )

Threadsafe

12.66.5.124 void seq64::sequence::remove_selected ( )

This is a new convenience function to fold in the push_undo() and mark_selected() calls. It makes the process slightly faster, as well.

Threadsafe Also makes the whole process threadsafe.

12.66.5.125 void seq64::sequence::unpaint_all ( )

Threadsafe

12.66.5.126 void seq64::sequence::unselect ( )

Threadsafe

12.66.5.127 void seq64::sequence::verify_and_link ( )

Threadsafe

12.66.5.128 void seq64::sequence::link_new ( )

Threadsafe

12.66.5.129 void seq64::sequence::zero_markers ( ) [inline]

This function is used when the sequencer stops. This function currently sets m_last_tick = 0, but we would like to avoid that if doing a pause, rather than a stop, of playback. However, commenting out this setting doesn't have any effect that we can see with a quick look at the user-interface.

12.66.5.130 void seq64::sequence::play_note_on (int *note*)

It flushes a note to the midibus to preview its sound, used by the virtual piano.

Threadsafe

Parameters

note	The note to play.

12.66.5.131 void seq64::sequence::play_note_off (int *note*)

Threadsafe

Parameters

note	The note to turn off.

12.66.5.132 void seq64::sequence::off_playing_notes ( )

This function does not bother checking if m_masterbus is a null pointer.

Threadsafe

12.66.5.133 void seq64::sequence::pause ( )

The reset() function is currently not called when pausing, but we still need the note-shutoff capability to prevent notes from lingering. Not that we do not call set_playing(false)... it disarms the sequence, which we do not want upon pausing.

12.66.5.134 void seq64::sequence::reset (bool *live_mode*)

Note that, in live mode, the user controls playback, while otherwise JACK or the performance/song editor controls playback. (We're still a bit confounded about these modes, alas.)

Parameters

live_mode	True if live mode is on. This means that JACK transport is not in control of playback.

12.66.5.135 void seq64::sequence::reset_draw_marker ( )

It resets the draw marker so that calls to get_next_note_event() will start from the first event.

Threadsafe

12.66.5.136 void seq64::sequence::reset_draw_trigger_marker ( )

Threadsafe

12.66.5.137 draw_type seq64::sequence::get_next_note_event (midipulse * *tick_s*, midipulse * *tick_f*, int * *note*, bool * *selected*, int * *velocity*)

When it has no more events, returns a false.

Parameters

out	*tick_s*	Provides a pointer destination for the start time.
out	*tick_f*	Provides a pointer destination for the finish time.
out	*note*	Provides a pointer destination for the note pitch value Probably should be a midibyte value.
out	*selected*	Provides a pointer destination for the selection status of the note.
out	*velocity*	Provides a pointer destination for the note velocity. Probably should be a midibyte value.

12.66.5.138 bool seq64::sequence::get_minmax_note_events (int & *lowest*, int & *highest*)

Todo For efficency, we should calculate this only when the event set changes, and save the results and return them if good.

Threadsafe

Parameters

lowest	A reference parameter to return the note with the lowest value. if there are no notes, then it is set to SEQ64_MIDI_COUNT_MAX-1.
highest	A reference parameter to return the note with the highest value. if there are no notes, then it is set to -1.

Returns

If there are no notes in the list, then false is returned, and the results should be disregarded.

12.66.5.139 bool seq64::sequence::get_next_event (midibyte *status*, midibyte *cc*, midipulse * *tick*, midibyte * *d0*, midibyte * *d1*, bool * *selected*)

Then set the rest of the parameters parameters using that event. If the status is the new value EVENT_ANY, then any event will be obtained.

Note the usage of event::is_desired_cc_or_not_cc(status, cc, *d0); Either we have a control change with the right CC or it's a different type of event.

Parameters

status	The type of event to be obtained. The special value EVENT_ANY can be provided so that no event statuses are filtered.
cc	The continuous controller value that might be desired.
tick	A pointer return value for the tick value of the next event found.
d0	A pointer return value for the first data value of the event.
d1	A pointer return value for the second data value of the event.
selected	A pointer return value for the is-selected status of the event.

12.66.5.140 bool seq64::sequence::get_next_event (midibyte * *status*, midibyte * *cc*)

Then set the status and control character parameters using that event.

12.66.5.141 bool seq64::sequence::get_next_trigger (midipulse * *tick_on*, midipulse * *tick_off*, bool * *selected*, midipulse * *tick_offset*)

12.66.5.142 void seq64::sequence::fill_container (midi_container & *c*, int *tracknumber*)

Note that some of the events might not come out in the same order they were stored in (we see that with program-change events.

Parameters

c	Provides the std::list object to push events to the front, which thus inserts them in backwards order. (These events are then popped back, which restores the order, with some exceptions).
tracknumber	Provides the track number. This number is masked into the track information.

12.66.5.143 void seq64::sequence::quantize_events (midibyte *status*, midibyte *cc*, midipulse *snap_tick*, int *divide*, bool *linked* = `false`)

One confusing things is why the original versions of the events don't seem to be deleted.

Parameters

status	Indicates the type of event to be quantized.
cc	The desired control-change to count, if the event is a control-change.
snap_tick	Provides the maximum amount to move the events. Actually, events are moved to the previous or next snap_tick value depend on whether they are halfway to the next one or not.
divide	A rough indicator of the amount of quantization. The only values used in the application seem to be either 1 or 2.
linked	False by default, this parameter indicates if marked events are to be relinked, as far as we can tell.

12.66.5.144 void seq64::sequence::push_quantize (midibyte *status*, midibyte *cc*, midipulse *snap_tick*, int *divide*, bool *linked* = `false`)

12.66.5.145 void seq64::sequence::transpose_notes (int *steps*, int *scale*)

If the scale value is 0, this is "no scale", which is the chromatic scale, where all 12 notes, including sharps and flats, are part of the scale.

Also, we've moved external calls to push_undo() into this function. The caller shouldn't have to do that.

Note

We noticed (ca 2016-06-10) that MIDI aftertouch events need to be transposed, but are not being transposed here. Assuming they are selectable (another question!), the test for note-on and note-off is not sufficient, and so has been replaced by a call to event::is_note_msg().

Parameters

steps	The number of steps to transpose the notes.
scale	The scale to make the notes adhere to while transposing.

12.66.5.146 midibyte seq64::sequence::musical_key ( ) const [inline]

12.66.5.147 void seq64::sequence::musical_key (int *key*) [inline]

12.66.5.148 midibyte seq64::sequence::musical_scale ( ) const [inline]

12.66.5.149 void seq64::sequence::musical_scale (int *scale*) [inline]

12.66.5.150 int seq64::sequence::background_sequence ( ) const [inline]

12.66.5.151 void seq64::sequence::background_sequence (int *bs*) [inline]

Disabling the sequence number (setting it to SEQ64_SEQUENCE_LIMIT) is valid.

12.66.5.152 void seq64::sequence::show_events ( ) const

12.66.5.153 void seq64::sequence::copy_events (const event_list & *newevents*)

Compare this function to the remove_all() function. Copying the container is a lot of work, but fairly fast, even with an std::multimap as the container.

Threadsafe Note that we had to consolidate the replacement of all the events in the container in order to prevent the "Save to Sequence" button in the eventedit object from causing the application to segfault. It would segfault when the mainwnd timer callback would fire, causing updates to the sequence's slot pixmap, which would then try to access deleted events. Part of the issue was that note links were dropped when copying the events, so now we call verify_and_link() to hopefully reconstitute the links.

Parameters

newevents	Provides the container of MIDI events that will completely replace the current container. Normally this container is supplied by the event editor, via the eventslots class.

12.66.5.154 midipulse seq64::sequence::note_off_margin ( ) const [inline]

12.66.5.155 void seq64::sequence::set_parent (perform * *p*) [private]

Remember that m_parent is not at all owned by the sequence. We just don't want to do all the work necessary to make it a reference, at this time.

Parameters

p	A pointer to the parent, assigned only if not already assigned.

12.66.5.156 void seq64::sequence::put_event_on_bus (event & *ev*) [private]

This function does not bother checking if m_masterbus is a null pointer.

Parameters

ev	The event to put on the buss.

Threadsafe

12.66.5.157 void seq64::sequence::set_trigger_offset (midipulse *trigger_offset*) [private]

If m_length is 0, then m_trigger_offset is simply set to the parameter.

Threadsafe

Parameters

trigger_offset	The full trigger offset to set.

12.66.5.158 void seq64::sequence::split_trigger (trigger & *trig,* midipulse *splittick*) [private]

This is the private overload of split_trigger.

Threadsafe

Parameters

trig	Provides the original trigger, and also holds the changes made to that trigger as it is shortened.
splittick	The position just after where the original trigger will be truncated, and the new trigger begins.

12.66.5.159 void seq64::sequence::adjust_trigger_offsets_to_length (midipulse *newlength*) [private]

Threadsafe

Might can get rid of this function?

Parameters

newlength	The new length of the adjusted trigger.

12.66.5.160 midipulse seq64::sequence::adjust_offset (midipulse *offset*) [private]

12.66.5.161 void seq64::sequence::remove (event_list::iterator *i*) [private]

We no longer bother checking the pointer. If it is bad, all hope is lost. If the event is a note off, and that note is currently playing, then send a note off.

Not threadsafe

Parameters

i	Provides the iterator to the event to remove from the event list.

12.66.5.162 void seq64::sequence::remove (event & *e*) [private]

Finds the given event in m_events, and removes the first iterator matching that. If there are events that would match after that, they remain in the container. This matches seq24 behavior.

Not threadsafe

Parameters

e	Provides a reference to the event to be removed.

12.66.5.163 void seq64::sequence::remove_all ( ) [private]

Unsets the modified flag. (Why?) Also see the new copy_events() function.

12.66.6 Friends And Related Function Documentation

12.66.6.1 friend class perform [friend]

12.66.6.2 friend class triggers [friend]

12.66.7 Field Documentation

12.66.7.1 event_list seq64::sequence::m_events_clipboard [static], [private]

Being static allows for copy/paste between patterns.

12.66.7.2 perform* seq64::sequence::m_parent [private]

We can use the rc_settings flag(s), but JACK could be disconnected. We could use a reference here, but, to avoid modifying the midifile class as well, we use a pointer. It is set in perform::add_sequence(). This member would also be using for passing modification status to the parent, so that the GUI code doesn't have to do it.

12.66.7.3 event_list seq64::sequence::m_events [private]

12.66.7.4 triggers seq64::sequence::m_triggers [private]

12.66.7.5 EventStack seq64::sequence::m_events_undo [private]

12.66.7.6 EventStack seq64::sequence::m_events_redo [private]

12.66.7.7 event_list::iterator seq64::sequence::m_iterator_draw [private]

12.66.7.8 midibyte seq64::sequence::m_midi_channel [private]

However, if this value is EVENT_NULL_CHANNEL (0xFF), then this sequence is an SMF 0 track, and has no single channel.

12.66.7.9 midibyte seq64::sequence::m_bus [private]

12.66.7.10 bool seq64::sequence::m_song_mute [private]

12.66.7.11 int seq64::sequence::m_notes_on [private]

12.66.7.12 mastermidibus* seq64::sequence::m_masterbus [private]

12.66.7.13 int seq64::sequence::m_playing_notes[SEQ64_MIDI_NOTES_MAX] [private]

It is used when muting, to shut off the notes that are playing.

12.66.7.14 bool seq64::sequence::m_was_playing [private]

12.66.7.15 bool seq64::sequence::m_playing [private]

12.66.7.16 bool seq64::sequence::m_recording [private]

12.66.7.17 bool seq64::sequence::m_quantized_rec [private]

12.66.7.18 bool seq64::sequence::m_thru [private]

12.66.7.19 bool seq64::sequence::m_queued [private]

12.66.7.20 bool seq64::sequence::m_dirty_main [private]

Provides the main dirtiness flag.

12.66.7.21 bool seq64::sequence::m_dirty_edit [private]

12.66.7.22 bool seq64::sequence::m_dirty_perf [private]

12.66.7.23 bool seq64::sequence::m_dirty_names [private]

12.66.7.24 bool seq64::sequence::m_editing [private]

12.66.7.25 bool seq64::sequence::m_raise [private]

It allows a sequence editor window to pop up if not already raised, in seqedit::timeout().

12.66.7.26 std::string seq64::sequence::m_name [private]

12.66.7.27 midipulse seq64::sequence::m_last_tick [private]

Provides the last tick played.

12.66.7.28 midipulse seq64::sequence::m_queued_tick [private]

12.66.7.29 midipulse seq64::sequence::m_trigger_offset [private]

12.66.7.30 const int seq64::sequence::m_maxbeats [private]

Hardwired to c_maxbeats at present.

12.66.7.31 int seq64::sequence::m_ppqn [private]

12.66.7.32 int seq64::sequence::m_seq_number [private]

This number is set in the perform::install_sequence() function.

12.66.7.33 midipulse seq64::sequence::m_length [private]

This value should be a power of two when used as a bar unit.

12.66.7.34 midipulse seq64::sequence::m_snap_tick [private]

It starts out as the value m_ppqn / 4.

12.66.7.35 int seq64::sequence::m_time_beats_per_measure [private]

Defaults to 4. Used by the sequence editor to mark things in correct time on the user-interface.

12.66.7.36 int seq64::sequence::m_time_beat_width [private]

Defaults to 4, which means the beat is a quarter note. A value of 8 would mean it is an eighth note. Used by the sequence editor to mark things in correct time on the user-interface.

12.66.7.37 int seq64::sequence::m_clocks_per_metronome [private]

This value provides the number of MIDI clocks between metronome clicks. The default value of this item is 24. It can also be read from some SMF 1 files, such as our hymne.mid example.

12.66.7.38 int seq64::sequence::m_32nds_per_quarter [private]

This value provides the number of notated 32nd notes in a MIDI quarter note (24 MIDI clocks). The usual (and default) value of this parameter is 8; some sequencers allow this to be changed.

12.66.7.39 int seq64::sequence::m_us_per_quarter_note [private]

This value can be extracted from the beats-per-minute value (mastermidibus::m_beats_per_minute), but here we set it to 0 by default, indicating that we don't want to write it. Otherwise, it can be read from a MIDI file, and saved here to be restored later.

12.66.7.40 int seq64::sequence::m_rec_vol [private]

12.66.7.41 midibyte seq64::sequence::m_musical_key [private]

If the value is SEQ64_KEY_OF_C, then there is no musical key to be set.

12.66.7.42 midibyte seq64::sequence::m_musical_scale [private]

If the value is the enumeration value c_scale_off, then there is no musical scale to be set.

12.66.7.43 int seq64::sequence::m_background_sequence [private]

If the value is greater than max_sequence(), then there is no background sequence to be set.

12.66.7.44 mutex seq64::sequence::m_mutex [mutable], [private]

Made mutable for use in certain locked getter functions.

12.66.7.45 const midipulse seq64::sequence::m_note_off_margin [private]

Also used when the user attempts to shrink a note to zero (or less than zero) length.

12.67 seq64::trigger Class Reference

This class hold a single trigger for a sequence object.

Public Member Functions

- trigger ()
  Initializes the trigger structure.
- bool operator< (const trigger &rhs)
  This operator compares only the m_tick_start members.
- midipulse tick_start () const
  'Getter' function for member m_tick_start
- void tick_start (midipulse s)
  'Setter' function for member m_tick_start
- void increment_tick_start (midipulse s)
  'Setter' function for member m_tick_start
- void decrement_tick_start (midipulse s)
  'Setter' function for member m_tick_start
- midipulse tick_end () const
  'Getter' function for member m_tick_end
- void tick_end (midipulse e)
  'Setter' function for member m_tick_end
- void increment_tick_end (midipulse s)
  'Setter' function for member m_tick_end
- void decrement_tick_end (midipulse s)
  'Setter' function for member m_tick_end
- midipulse offset () const
  'Getter' function for member m_offset
- void offset (midipulse o)
  'Setter' function for member m_offset
- void increment_offset (midipulse s)
  'Setter' function for member m_offset
- void decrement_offset (midipulse s)
  'Setter' function for member m_offset
- bool selected () const
  'Getter' function for member m_selected
- void selected (bool s)
  'Setter' function for member m_selected

Private Attributes

- midipulse m_tick_start
  Provides the starting tick for this trigger.
- midipulse m_tick_end
  Provides the ending tick for this trigger.
- midipulse m_offset
  Provides the offset for this trigger.
- bool m_selected
  Indicates that the trigger is part of a selection.

12.67.1 Detailed Description

This class is used in playback, and is contained in the triggers class.

12.67.2 Constructor & Destructor Documentation

12.67.2.1 seq64::trigger::trigger ( ) [inline]

12.67.3 Member Function Documentation

12.67.3.1 bool seq64::trigger::operator< (const trigger & *rhs*) [inline]

Parameters

rhs	The "right-hand side" of the less-than operation.

Returns

Returns true if m_tick_start is less than rhs's.

12.67.3.2 midipulse seq64::trigger::tick_start ( ) const [inline]

12.67.3.3 void seq64::trigger::tick_start (midipulse *s*) [inline]

12.67.3.4 void seq64::trigger::increment_tick_start (midipulse *s*) [inline]

12.67.3.5 void seq64::trigger::decrement_tick_start (midipulse *s*) [inline]

12.67.3.6 midipulse seq64::trigger::tick_end ( ) const [inline]

12.67.3.7 void seq64::trigger::tick_end (midipulse *e*) [inline]

12.67.3.8 void seq64::trigger::increment_tick_end (midipulse *s*) [inline]

12.67.3.9 void seq64::trigger::decrement_tick_end (midipulse *s*) [inline]

12.67.3.10 midipulse seq64::trigger::offset ( ) const [inline]

12.67.3.11 void seq64::trigger::offset (midipulse *o*) [inline]

12.67.3.12 void seq64::trigger::increment_offset (midipulse *s*) [inline]

12.67.3.13 void seq64::trigger::decrement_offset (midipulse *s*) [inline]

12.67.3.14 bool seq64::trigger::selected ( ) const [inline]

12.67.3.15 void seq64::trigger::selected (bool *s*) [inline]

12.67.4 Field Documentation

12.67.4.1 midipulse seq64::trigger::m_tick_start [private]

12.67.4.2 midipulse seq64::trigger::m_tick_end [private]

12.67.4.3 midipulse seq64::trigger::m_offset [private]

12.67.4.4 bool seq64::trigger::m_selected [private]

12.68 seq64::triggers Class Reference

The triggers class is a receptable the triggers that can be used with a sequence object.

Public Types

- typedef std::list< trigger > List

  Exposes the triggers type, currently needed for midi_container only.

Public Member Functions

- triggers (sequence &parent)

  Principal constructor.
- ~triggers ()

  A rote destructor.
- triggers & operator= (const triggers &rhs)

  Principal assignment operator.
- void set_ppqn (int ppqn)

  'Setter' function for member m_ppqn We have to set this value after construction for best safety.
- void set_length (int len)

  'Setter' function for member m_length We have to set this value after construction for best safety.
- List & triggerlist ()

  'Getter' function for member m_triggers
- void push_undo ()

  Pushes the list-trigger into the trigger undo-list, then flags each item in the undo-list as unselected.
- void pop_undo ()

  If the trigger undo-list has any items, the list-trigger is pushed into the redo list, the top of the undo-list is coped into the list-trigger, and then pops from the undo-list.
- void print (const std::string &seqname) const

  Prints a list of the currently-held triggers.
- bool play (midipulse &starttick, midipulse &endtick)

  If playback-mode (song mode) is in force, that is, if using in-triggers and on/off triggers, this function handles that kind of playback.

- void add (midipulse tick, midipulse len, midipulse offset=0, bool adjustoffset=true)

  Adds a trigger.
- void adjust_offsets_to_length (midipulse newlen)

  Adjusts trigger offsets to the length specified for all triggers, and undo triggers.
- void split (midipulse tick)

  Splits the first trigger that brackets the splittick parameter.
- void split (trigger &trig, midipulse splittick)

  Splits the trigger given by the parameter into two triggers.
- void grow (midipulse tickfrom, midipulse tickto, midipulse length)

  Grows a trigger.
- void remove (midipulse tick)

  Deletes the first trigger that brackets the given tick from the trigger-list.
- bool get_state (midipulse tick)

  Checks the list of triggers against the given tick.
- bool select (midipulse tick)

  Checks the list of triggers against the given tick.
- bool unselect ()

  Unselects all triggers.
- bool intersect (midipulse position, midipulse &start, midipulse &end)

  This function examines each trigger in the trigger list.
- void remove_selected ()

  Deletes the first selected trigger that is found.
- void copy_selected ()

  Copies the first selected trigger that is found.
- void paste ()

  If there is a copied trigger, then this function grabs it from the trigger clipboard and adds it.
- bool move_selected (midipulse tick, bool adjustoffset, int which=2)

  Moves selected triggers as per the given parameters.
- midipulse get_selected_start ()

  Gets the selected trigger's start tick.
- midipulse get_selected_end ()

  Gets the selected trigger's end tick.
- midipulse get_maximum ()

  Get the ending value of the last trigger in the trigger-list.
- void move (midipulse starttick, midipulse distance, bool direction)

  Moves triggers in the trigger-list.
- void copy (midipulse starttick, midipulse distance)

  Not sure what these diagrams are for yet.
- void clear ()

  Clears the whole list of triggers.
- bool next (midipulse *tick_on, midipulse *tick_off, bool *selected, midipulse *tick_offset)

  Get the next trigger in the trigger list, and set the parameters based on that trigger.
- trigger next_trigger ()

  Get the next trigger in the trigger list.
- void reset_draw_trigger_marker ()

  Sets the draw-trigger iterator to the beginning of the trigger list.

Private Types

- typedef std::stack< List > Stack

Private Member Functions

- midipulse adjust_offset (midipulse offset)

  Adjusts the given offset by mod'ing it with m_length and adding m_length if needed, and returning the result.

Private Attributes

- sequence & m_parent

  Holds a reference to the parent sequence object that owns this trigger object.
- List m_triggers

  This list holds the current pattern/triggers events.
- trigger m_clipboard

  This item holds a single copied trigger, to be pasted later.
- Stack m_undo_stack

  Handles the undo list for a series of operations on triggers.
- Stack m_redo_stack

  Handles the redo list for a series of operations on triggers.
- List::iterator m_iterator_play_trigger

  An iterator for cycling through the triggers during playback.
- List::iterator m_iterator_draw_trigger

  An iterator for cycling through the triggers during drawing.
- bool m_trigger_copied

  Set to true if there is an active trigger in the trigger clipboard.
- int m_ppqn

  Holds the value of the PPQN from the parent sequence, for easy access.
- int m_length

  Holds the value of the length from the parent sequence, for easy access.

12.68.1 Member Typedef Documentation

12.68.1.1 typedef std::list<trigger> seq64::triggers::List

12.68.1.2 typedef std::stack<List> seq64::triggers::Stack [private]

12.68.2 Constructor & Destructor Documentation

12.68.2.1 seq64::triggers::triggers (sequence & *parent*)

Parameters

parent	The triggers object often needs to tell its parent sequence object what to do (such as stop playing).

12.68.2.2 seq64::triggers::~triggers ( )

12.68.3 Member Function Documentation

12.68.3.1 triggers & seq64::triggers::operator= (const triggers & *rhs*)

Follows the stock rules for such an operator, but does a little more then just assign member values.

FIXED, BEWARE: Currently, it does not assign them all, so we should create a partial_copy() function to do this work, and use it where it is needed.

Parameters

rhs	Provides the "right-hand side" of the assignment operation.

Returns

Returns a reference to self, for use in concatenated assignment operations.

12.68.3.2 void seq64::triggers::set_ppqn (int *ppqn*) [inline]

12.68.3.3 void seq64::triggers::set_length (int *len*) [inline]

Also, there a chance that the length of the parent might change from time to time. Currently, only the sequence constructor and midifile call this function.

12.68.3.4 List& seq64::triggers::triggerlist ( ) [inline]

12.68.3.5 void seq64::triggers::push_undo ( )

12.68.3.6 void seq64::triggers::pop_undo ( )

12.68.3.7 void seq64::triggers::print (const std::string & *seqname*) const

Parameters

seqname	A tag name to accompany the print-out, for the human to read.

12.68.3.8 bool seq64::triggers::play (midipulse & *start_tick*, midipulse & *end_tick*)

This is a new function for sequence::play() to call.

The for-loop goes through all the triggers, determining if there is are trigger start/end values before the *end_tick*. If so, then the trigger state is set to true (start only within the tick range) or false (end is within the tick range), and the trigger tick is set to start or end. The first start or end trigger that is past the end tick cause the search to end.

If the trigger state has changed, then the start/end ticks are passed back to the sequence, and the trigger offset is adjusted.

Parameters

start_tick	Provides the starting tick value, and returns the modified value as a side-effect.
end_tick	Provides the ending tick value, and returns the modified value as a side-effect.

Returns

Returns true if we're through playing the frame (trigger turning off), and the caller should stop the playback.

12.68.3.9 void seq64::triggers::add (midipulse *tick*, midipulse *len*, midipulse *offset* = `0`, bool *fixoffset* = `true`)

What is this?

```
is    ie
<      ><         ><         >
es              ee
<                >
XX
es ee
<   >
<>
es    ee
<       >
<    >
es     ee
<       >
<    >
```

Parameters

tick	Provides the tick (pulse) time at which the trigger goes on.
len	Provides the length of the trigger. This value is actually calculated from the "on" value minus the "off" value read from the MIDI file.
offset	This value specifies the offset of the trigger. It is a feature of the c_triggers_new that c_triggers doesn't have. It is the third value in the trigger specification of the Sequencer64 MIDI file.
fixoffset	If true, the offset parameter is modified by adjust_offset() first. We think that basically makes sure it is positive.

12.68.3.10 void seq64::triggers::adjust_offsets_to_length (midipulse *newlength*)

Parameters

newlength	Provides the length to which to adjust the offsets.

COMMON CODE?

COMMON CODE?

12.68.3.11 void seq64::triggers::split (midipulse *splittick*)

This is the first trigger where splittick is greater than L and less than R.

Parameters

splittick	Provides the tick that must be bracketed for the split to be made.

12.68.3.12 void seq64::triggers::split (trigger & *trig,* midipulse *splittick*)

The original trigger ends 1 tick before the splittick parameter, and the new trigger starts at splittick and ends where the original trigger ended.

Parameters

trig	Provides the original trigger, and also holds the changes made to that trigger as it is shortened, as a side-effect.
splittick	The position just after where the original trigger will be truncated, and the new trigger begins.

12.68.3.13 void seq64::triggers::grow (midipulse *tickfrom,* midipulse *tickto,* midipulse *len*)

This function looks for the first trigger where the tickfrom parameter is between the trigger's tick-start and tick-end values. If found then the trigger's start is moved back to tickto, if necessary, or the trigger's end is moved to tickto plus the length parameter, if necessary.

Then this new trigger is added, and the function breaks from the search loop.

Parameters

tickfrom	The desired from-value back which to expand the trigger, if necessary.
tickto	The desired to-value towards which to expand the trigger, if necessary.
len	The additional length to append to tickto for the check.

12.68.3.14 void seq64::triggers::remove (midipulse *tick*)

Parameters

tick	Provides the tick to be examined.

12.68.3.15 bool seq64::triggers::get_state (midipulse *tick*)

If any trigger is found to bracket that tick, then true is returned.

Parameters

tick	Provides the tick of interest.

Returns

Returns true if a trigger is found that brackets the given tick.

12.68.3.16 bool seq64::triggers::select (midipulse *tick*)

If any trigger is found to bracket that tick, then true is returned, and the trigger is marked as selected.

Parameters

tick	Provides the tick of interest.

Returns

Returns true if a trigger is found that brackets the given tick.

12.68.3.17 bool seq64::triggers::unselect ( )

Returns

Always returns false.

12.68.3.18 bool seq64::triggers::intersect (midipulse *position,* midipulse & *start,* midipulse & *ender*)

If the given position is between the current trigger's tick-start and tick-end values, the these values are copied to the start and end parameters, respectively, and then we exit.

Parameters

position	The position to examine.
start	The destination for the starting tick (m_tick_start) of the matching trigger.
ender	The destination for the ending tick (m_tick_end) of the matching trigger.

Returns

Returns true if a trigger was found whose start/end ticks contained the position. Otherwise, false is returned, and the start and end return parameters should not be used.

12.68.3.19 void seq64::triggers::remove_selected ( )

12.68.3.20 void seq64::triggers::copy_selected ( )

12.68.3.21 void seq64::triggers::paste ( )

It pastes at the copy end.

12.68.3.22 bool seq64::triggers::move_selected (midipulse *tick,* bool *fixoffset,* int *which* = 2)

```
          mintick][0                1][maxtick
                          2


The \a which parameter has three possible values:

-#  If we are moving the 0, use first as offset.
-#  If we are moving the 1, use the last as the offset.
-#  If we are moving both (2), use first as offset.
```

Parameters

tick	The tick at which the trigger starts.
fixoffset	Set to true if the offset is to be adjusted.
which	Selects which movement will be done, as discussed above.

Returns

Returns true if there was room to move. Otherwise, false is returned. We need this feature to support keystoke movement of a selected trigger in the perfroll window, and keep it from continually incrementing when there can be no more movement. This causes moving the other direction to be delayed while the accumulating movement counter is used up. However, right now we can't rely on this result, and ignore it. There may be no way around this minor issue.

12.68.3.23 midipulse seq64::triggers::get_selected_start ( )

We guess this ends up selecting only one trigger, otherwise only the last selected one would effectively set the result.

Returns

Returns the tick_start() value of the last-selected trigger. If no triggers are selected, then midipulse(-1) is returned.

12.68.3.24 midipulse seq64::triggers::get_selected_end ( )

Returns

Returns the tick_end() value of the last-selected trigger. If no triggers are selected, then midipulse(-1) is returned.

12.68.3.25 midipulse seq64::triggers::get_maximum ( )

Returns

Returns the tick-end for the last trigger, if available. Otherwise, 0 is returned.

12.68.3.26 void seq64::triggers::move (midipulse *starttick,* midipulse *distance,* bool *direction*)

There's no way to optimize this by saving tick values, as they are potentially modified at each step.

Parameters

starttick	The current location of the triggers.
distance	The distance away from the current location to which to move the triggers.
direction	If true, the triggers are moved forward. If false, the triggers are moved backward.

12.68.3.27 void seq64::triggers::copy (midipulse *starttick*, midipulse *distance*)

```
... a
[      ][      ]
...
... a
...

5   7    play
3        offset
8   10   play

X...X...X...X...X...X...X...X...X...X...
L       R
[        ] [     ]  []  orig
[                   ]

        <<
        [     ]    [  ][ ]  [] split on the R marker, shift first
        [     ]        [     ]
        delete middle
        [     ][ ]  []         move ticks
        [     ][     ]

        L       R
        [     ][ ] [     ]  [] split on L
        [     ][             ]

        [     ]        [ ] [     ]  [] increase all after L
        [     ]        [             ]
```

Copies triggers to a point distant from a given tick.

Parameters

starttick	The current location of the triggers.
distance	The distance away from the current location to which to copy the triggers.

12.68.3.28 void seq64::triggers::clear ( ) [inline]

12.68.3.29 bool seq64::triggers::next (midipulse * *tick_on*, midipulse * *tick_off*, bool * *selected*, midipulse * *offset*)

Todo It would be a bit simpler to simply return a trigger object, wouldn't it?

Parameters

tick_on	Return value for the retrieval of the starting tick for the trigger.
tick_off	Return value for the retrieval of the ending tick for the trigger.
selected	Return value for the retrieval of the is-selected flag for the trigger.
offset	Return value for the retrieval of the offset for the trigger.

Returns

Returns true if a trigger was found. If false, the caller cannot rely on the values returned through the return parameters.

Side-effect(s) The value of the m_iterator_draw_trigger member will be altered by this call, unless pointing to the end of the triggerlist, or if there are no triggers.

12.68.3.30 trigger seq64::triggers::next_trigger ( )

Returns

Returns the next trigger. If there is none, a default trigger object is returned.

12.68.3.31 void seq64::triggers::reset_draw_trigger_marker ( ) [inline]

12.68.3.32 midipulse seq64::triggers::adjust_offset (midipulse *offset*) [private]

Parameters

offset	Provides the offset, mod'ed against m_length, used to adjust the offset.

Returns

Returns the new offset. However, if m_length is 0, no change is made, and the original offset is returned.

12.68.4 Field Documentation

12.68.4.1 sequence& seq64::triggers::m_parent [private]

12.68.4.2 List seq64::triggers::m_triggers [private]

12.68.4.3 trigger seq64::triggers::m_clipboard [private]

12.68.4.4 Stack seq64::triggers::m_undo_stack [private]

12.68.4.5 Stack seq64::triggers::m_redo_stack [private]

12.68.4.6 List::iterator seq64::triggers::m_iterator_play_trigger [private]

12.68.4.7 List::iterator seq64::triggers::m_iterator_draw_trigger [private]

12.68.4.8 bool seq64::triggers::m_trigger_copied [private]

12.68.4.9 int seq64::triggers::m_ppqn [private]

This should not change, but we have to set it after construction, and so we provide a setter for it, set_ppqn(), called by the sequence constructor.

12.68.4.10 int seq64::triggers::m_length [private]

This might change, we're not yet sure.

12.69 seq64::user_instrument Class Reference

Provides data about the MIDI instruments, readable from the "user" configuration file.

Public Member Functions

- user_instrument (const std::string &name="")

  Default constructor.
- user_instrument (const user_instrument &rhs)

  Copy constructor.
- user_instrument & operator= (const user_instrument &rhs)

  Principal assignment operator.
- bool is_valid () const

  'Getter' function for member m_is_valid
- void set_defaults ()

  Sets the default values.
- const std::string & name () const

  'Getter' function for member m_instrument_def.instrument (name of instrument)
- int controller_count () const

  'Getter' function for member m_controller_count This function returns the number of active controllers.
- int controller_max () const

  'Getter' function for member MIDI_CONTROLLER_MAX This function returns the maximum number of controllers, active or inactive.
- const std::string & controller_name (int c) const

  'Getter' function for member m_instrument_def.controllers[c]
- bool controller_active (int c) const

  'Getter' function for member m_instrument_def.controllers_active[c]
- void set_controller (int c, const std::string &cname, bool isactive)

  'Setter' function for member m_instrument_def.controllers[c] and .controllers_active[c] Only sets the controller values if the object is already valid.

Private Member Functions

- void set_name (const std::string &instname)

  'Setter' function for member m_instrument_def.instrument If the name parameter is not empty, the validity flag is set to true, otherwise it is set to false.
- void copy_definitions (const user_instrument &rhs)

  Copies the array members from one instance of user_instrument to this one.

Private Attributes

- bool m_is_valid

  Provides a validity flag, useful in returning a reference to a bogus object for internal error-check.
- int m_controller_count

  Provides the actual number of non-default controllers actually set.
- user_instrument_t m_instrument_def

  The instance of the structure that this class wraps.

12.69.1 Detailed Description

Will later make the size adjustable, if it makes sense to do so.

12.69.2 Constructor & Destructor Documentation

12.69.2.1 seq64::user_instrument::user_instrument (const std::string & *name* = " ")

Fills in the defaults for the instrument definition, sets its name, and provides some light validation.

Parameters

name	The name of the instrument, valid only if it is not empty.

12.69.2.2 seq64::user_instrument::user_instrument (const user_instrument & *rhs*)

Parameters

rhs	The sources of the data for the copy.

12.69.3 Member Function Documentation

12.69.3.1 user_instrument & seq64::user_instrument::operator= (const user_instrument & *rhs*)

Parameters

rhs	The sources of the data for the assignment.

Returns

Returns a reference to this object.

12.69.3.2 bool seq64::user_instrument::is_valid ( ) const [inline]

12.69.3.3 void seq64::user_instrument::set_defaults ( )

Also invalidates the object.

12.69.3.4 const std::string& seq64::user_instrument::name ( ) const [inline]

12.69.3.5 int seq64::user_instrument::controller_count ( ) const [inline]

12.69.3.6 int seq64::user_instrument::controller_max ( ) const [inline]

Remember that the controller numbers for each MIDI instrument range from 0 to 127 (MIDI_CONTROLLER_MAX-1).

12.69.3.7 const std::string & seq64::user_instrument::controller_name (int *c*) const

Parameters

c	The index of the desired controller.

Returns

The name of the desired controller has is returned. If the index c is out of range, or the object is not valid, then a reference to an internal, empty string is returned.

12.69.3.8 bool seq64::user_instrument::controller_active (int *c*) const

Parameters

c	The index of the desired controller.

Returns

The status of the desired controller has is returned. If the index c is out of range, or the object is not valid, then false is returned.

12.69.3.9 void seq64::user_instrument::set_controller (int *c,* const std::string & *cname,* bool *isactive*)

Parameters

c	The index of the desired controller.
cname	The name of the controller to be set as the controller name.
isactive	A flag that indicates if the desired controller is active.

12.69.3.10 void seq64::user_instrument::set_name (const std::string & *instname*) [private]

Too tricky?

Parameters

instname	The name of the instrument, valid only if it is not empty.

12.69.3.11 void seq64::user_instrument::copy_definitions (const user_instrument & *rhs*) [private]

Does not include the validity flag.

Parameters

rhs	The sources of the data for the partial copy.

12.69.4 Field Documentation

12.69.4.1 bool seq64::user_instrument::m_is_valid [private]

Callers should check this flag via the is_valid() accessor before using this object. This flag is set to true when any valid member assignment occurs via a public setter call. However, setting an empty name for the instrument member will render the object invalid.

12.69.4.2 int seq64::user_instrument::m_controller_count [private]

Often, the "user" configuration file has only a few out of the 128 assigned explicitly.

12.69.4.3 user_instrument_t seq64::user_instrument::m_instrument_def [private]

12.70 seq64::user_instrument_t Struct Reference

This structure corresponds to `[user-instrument-N]` definitions in the `~/.seq24usr` or `~/.config/sequencer64/seq24usr` file.

Data Fields

- std::string instrument

  Provides the name of the "instrument" being supported.
- std::string controllers [SEQ64_MIDI_CONTROLLER_MAX]

  Provides a list of up to 128 controllers (e.g.
- bool controllers_active [SEQ64_MIDI_CONTROLLER_MAX]

  Provides a flag that indicates if each of up to 128 controller is active and supported.

12.70.1 Field Documentation

12.70.1.1 std::string seq64::user_instrument_t::instrument

Do not confuse "instrument" with "program" here. An "instrument" is most likely a hardware MIDI sound-box (though it could be a software synthesizer as well.

12.70.1.2 std::string seq64::user_instrument_t::controllers[SEQ64_MIDI_CONTROLLER_MAX]

"Modulation"). If a controller isn't present, or if General MIDI is in force, this name might be empty.

12.70.1.3 bool seq64::user_instrument_t::controllers_active[SEQ64_MIDI_CONTROLLER_MAX]

If false, it might be an unsupported controller or a General MIDI device.

12.71 seq64::user_midi_bus Class Reference

Provides data about the MIDI busses, readable from the "user" configuration file.

Public Member Functions

- user_midi_bus (const std::string &name="")

  Default constructor.
- user_midi_bus (const user_midi_bus &rhs)

  Copy constructor.
- user_midi_bus & operator= (const user_midi_bus &rhs)

  Principal assignment operator.
- bool is_valid () const

  'Getter' function for member m_is_valid
- void set_defaults ()

  Sets the default values.
- const std::string & name () const

  'Getter' function for member m_midi_bus_def.alias (name of alias)
- int channel_count () const

  'Getter' function for member m_channel_count
- int channel_max () const

  'Getter' function for member SEQ64_MIDI_BUS_CHANNEL_MAX
- int instrument (int channel) const

  'Getter' function for member m_midi_bus_def.instrument[channel]
- void set_instrument (int channel, int instrum)

  'Getter' function for member m_midi_bus_def.instrument[channel]

Private Member Functions

- void set_name (const std::string &name)

  'Setter' function for member m_midi_bus_def.alias (name of alias) Also sets the validity flag according to the emptiness of the name parameter.
- void copy_definitions (const user_midi_bus &rhs)

  Copies the member fields from one instance of user_midi_bus to this one.

Private Attributes

- bool m_is_valid

  Provides a validity flag, useful in returning a reference to a bogus object for internal error-check.
- int m_channel_count

  Provides the actual number of non-default buss channels actually set.
- user_midi_bus_t m_midi_bus_def

  The instance of the structure that this class wraps.

12.71.1 Detailed Description

Will later make the size adjustable, if it makes sense to do so.

12.71.2 Constructor & Destructor Documentation

12.71.2.1 seq64::user_midi_bus::user_midi_bus (const std::string & *name* = " ")

Parameters

name	The name of the buss, valid only if it is not empty.

12.71.2.2 seq64::user_midi_bus::user_midi_bus (const user_midi_bus & *rhs*)

Parameters

rhs	The sources of the data for the copy.

12.71.3 Member Function Documentation

12.71.3.1 user_midi_bus & seq64::user_midi_bus::operator= (const user_midi_bus & *rhs*)

Parameters

rhs	The sources of the data for the assignment.

Returns

Returns a reference to this object.

12.71.3.2 bool seq64::user_midi_bus::is_valid ( ) const [inline]

12.71.3.3 void seq64::user_midi_bus::set_defaults ( )

Also invalidates the object. All 16 of the channels are set to SEQ64_GM_INSTRUMENT_FLAG (-1).

12.71.3.4 const std::string& seq64::user_midi_bus::name ( ) const [inline]

12.71.3.5 int seq64::user_midi_bus::channel_count ( ) const [inline]

Returns

This function returns the number of channels. Basically this value is always the same as that returned by channel_max(), but this pair of functions is consistent with the count functions in the user_instrument class.

12.71.3.6 int seq64::user_midi_bus::channel_max ( ) const [inline]

Returns

Returns the maximum number of MIDI buss channels. Remember that the instrument channels for each MIDI buss range from 0 to 15 (MIDI_BUS_CHANNEL_MAX-1).

12.71.3.7 int seq64::user_midi_bus::instrument (int *channel*) const

Parameters

channel	Provides the desired buss channel number.

Returns

The instrument number of the desired buss channel is returned. If the channel number is out of range, or the object is not valid, then SEQ64_GM_INSTRUMENT_FLAG (-1) is returned.

12.71.3.8 void seq64::user_midi_bus::set_instrument (int *channel,* int *instrum*)

Does not alter the validity flag, just checks it.

Parameters

channel	Provides the desired buss channel number.
instrum	Provides the instrument number to set that channel to.

12.71.3.9 void seq64::user_midi_bus::set_name (const std::string & *name*) [inline], [private]

12.71.3.10 void seq64::user_midi_bus::copy_definitions (const user_midi_bus & *rhs*) [private]

Does not include the validity flag.

12.71.4 Field Documentation

12.71.4.1 bool seq64::user_midi_bus::m_is_valid [private]

Callers should check this flag via the is_valid() accessor before using this object. This flag is set to true when any valid member assignment occurs via a public setter call.

12.71.4.2 int seq64::user_midi_bus::m_channel_count [private]

Often, the "user" configuration file has only a few out of the 16 assigned explicitly.

12.71.4.3 user_midi_bus_t seq64::user_midi_bus::m_midi_bus_def [private]

12.72 seq64::user_midi_bus_t Struct Reference

This structure corresponds to `[user-midi-bus-0]` definitions in the `~/.seq24usr` ("user") file (`~/.config/sequencer64/sequencer64.usr` in the latest version of the application).

Data Fields

- std::string alias

  Provides the user's desired name for the MIDI bus.
- int instrument [SEQ64_MIDI_BUS_CHANNEL_MAX]

  Provides an implicit list of MIDI channels from 0 to 15 (1 to 16) and the "instrument" number assigned to each channel.

12.72.1 Field Documentation

12.72.1.1 std::string seq64::user_midi_bus_t::alias

For example, "2x2 A" for some kind of MIDI card or USB MIDI cable. If manual-alsa-ports is enabled, this could be something like "[0] seq24 0", and that is what should be shown in that case.

12.72.1.2 int seq64::user_midi_bus_t::instrument[SEQ64_MIDI_BUS_CHANNEL_MAX]

Note that the "instrument" is not a MIDI program number. Instead, it is the number associated with a "user-instrument" section in the "user" configuration file.

12.73 seq64::user_settings Class Reference

Holds the current values of sequence settings and settings that can modify the number of sequences and the configuration of the user-interface.

Public Member Functions

- user_settings ()

  Default constructor.
- user_settings (const user_settings &rhs)

  Copy constructor.
- user_settings & operator= (const user_settings &rhs)

  Principal assignment operator.
- void set_defaults ()

  Sets the default values.
- void normalize ()

  Calculate the derived values from the already-set values.
- bool add_bus (const std::string &alias)

  Adds a user buss to the container, but only does so if the name parameter is not empty.
- bool add_instrument (const std::string &instname)

  Adds a user instrument to the container, but only does so if the name parameter is not empty.
- const user_midi_bus & bus (int index)

  'Getter' function for member Unlike the non-const version this function is public.
- const user_instrument & instrument (int index)

  'Getter' function for member Unlike the non-const version this function is public.
- int bus_count () const

  'Getter' function for member m_midi_buses.size()
- void set_bus_instrument (int index, int channel, int instrum)

  'Getter' function for member m_midi_buses[index].instrument[channel] Currently this function is used, in the userfile::parse() function.
- int bus_instrument (int buss, int channel)

  'Getter' function for member m_midi_buses[buss].instrument[channel]
- const std::string & bus_name (int buss)

  'Getter' function for member m_midi_buses[buss].name
- int instrument_count () const

  'Getter' function for member m_instruments.size()
- void set_instrument_controllers (int index, int cc, const std::string &ccname, bool isactive)

  'Setter' function for member m_midi_instrument_defs[index].controllers, controllers_active
- const std::string & instrument_name (int instrum)

  'Getter' function for member m_instruments[instrument].instrument (name of instrument)
- const std::string & instrument_name (int buss, int channel)

  Gets the correct instrument number from the buss and channel, and then looks up the name of the instrument.
- bool instrument_controller_active (int instrum, int cc)

  'Getter' function for member m_instruments[instrument].controllers_active[controller]
- bool controller_active (int buss, int channel, int cc)

  A convenience function so that the caller doesn't have to get the instrument number from the bus_instrument() member function.
- const std::string & instrument_controller_name (int instrum, int cc)

  'Getter' function for member m_instruments[instrument].controllers_active[controller]
- const std::string & controller_name (int buss, int channel, int cc)

  'Getter' function for member m_instruments[instrument].controllers_active[controller] A convenience function so that the caller doesn't have to get the instrument number from the bus_instrument() member function.
- int grid_style () const

  'Getter' function for member m_grid_style Checks for normal style.
- bool grid_is_normal () const

  'Getter' function for member m_grid_style Checks for normal style.
- bool grid_is_white () const

'Getter' function for member m_grid_style Checks for the white style.

- bool grid_is_black () const

  'Getter' function for member m_grid_style Checks for the black style.

- int grid_brackets () const

  'Getter' function for member m_grid_brackets

- int mainwnd_rows () const

  'Getter' function for member m_mainwnd_rows

- int mainwnd_cols () const

  'Getter' function for member m_mainwnd_cols

- int seqs_in_set () const

  'Getter' function for member m_seqs_in_set, dependent member

- int gmute_tracks () const

  'Getter' function for member m_gmute_tracks, dependent member

- int max_sets () const

  'Getter' function for member m_max_sets

- int max_sequence () const

  'Getter' function for member m_max_sequence, dependent member

- int text_x () const

  'Getter' function for member m_text_x, not user modifiable, not saved

- int text_y () const

  'Getter' function for member m_text_y, not user modifiable, not saved

- int seqchars_x () const

  'Getter' function for member m_seqchars_x, not user modifiable, not saved

- int seqchars_y () const

  'Getter' function for member m_seqchars_y, not user modifiable, not saved

- int seqarea_x () const

  'Getter' function for member m_seqarea_x, not user modifiable, not saved

- int seqarea_y () const

  'Getter' function for member m_seqarea_y, not user modifiable, not saved

- int seqarea_seq_x () const

  'Getter' function for member m_seqarea_seq_x, not user modifiable, not saved

- int seqarea_seq_y () const

  'Getter' function for member m_seqarea_seq_y, not user modifiable, not saved

- int mainwid_border () const

  'Getter' function for member m_mainwid_border

- int mainwid_spacing () const

  'Getter' function for member m_mainwid_spacing

- int mainwid_x () const

  'Getter' function for member m_mainwid_x, dependent member

- int mainwid_y () const

  'Getter' function for member m_mainwid_y, dependent member

- int control_height () const

  'Getter' function for member m_control_height

- int zoom () const

  'Getter' function for member m_current_zoom

- void zoom (int value)

  'Setter' function for member m_current_zoom This value is not modified unless the value parameter is between 1 and 512, inclusive.

- bool global_seq_feature () const

  'Getter' function for member m_global_seq_feature_save

- void global_seq_feature (bool flag)

'Setter' function for member m_global_seq_feature_save

- int seqedit_scale () const

  'Getter' function for member m_seqedit_scale

- void seqedit_scale (int scale)

  'Setter' function for member m_seqedit_scale

- int seqedit_key () const

  'Getter' function for member m_seqedit_key

- void seqedit_key (int key)

  'Setter' function for member m_seqedit_key

- int seqedit_bgsequence () const

  'Getter' function for member m_seqedit_bgsequence

- void seqedit_bgsequence (int seqnum)

  'Setter' function for member m_seqedit_bgsequence Note that SEQ64_IS_LEGAL_SEQUENCE() allows the SE↩ Q64_SEQUENCE_LIMIT (0x800 = 2048) value, to turn off the use of a background sequence.

- bool use_new_font () const

  'Getter' function for member m_use_new_font

- bool allow_two_perfedits () const

  'Getter' function for member m_allow_two_perfedits

- int perf_h_page_increment () const

  'Getter' function for member m_h_perf_page_increment

- int perf_v_page_increment () const

  'Getter' function for member m_v_perf_page_increment

- bool progress_bar_colored () const

  'Getter' function for member m_progress_bar_colored

- bool progress_bar_thick () const

  'Getter' function for member m_progress_bar_thick

- int window_redraw_rate () const

  'Getter' function for member m_window_redraw_rate_ms

- bool save_user_config () const

  'Getter' function for member m_save_user_config

- void save_user_config (bool flag)

  'Setter' function for member m_save_user_config

- int midi_ppqn () const

  'Getter' function for member m_midi_ppqn

- int midi_beats_per_bar () const

  'Getter' function for member m_midi_beats_per_measure

- int midi_beats_per_minute () const

  'Getter' function for member m_midi_beats_per_minute

- int midi_beat_width () const

  'Getter' function for member m_midi_beat_width

- char midi_buss_override () const

  'Getter' function for member m_midi_buss_override

- int min_zoom () const

  'Getter' function for member mc_min_zoom

- int max_zoom () const

  'Getter' function for member mc_max_zoom

- int baseline_ppqn () const

  'Getter' function for member mc_baseline_ppqn

- void use_new_font (bool flag)

  'Setter' function for member m_use_new_font

- void allow_two_perfedits (bool flag)

Sets the value of allowing two perfedits to be created and shown to the user.

- void perf_h_page_increment (int inc)

  Sets the horizontal page increment size for the horizontal scrollbar of a perfedit window.
- void perf_v_page_increment (int inc)

  Sets the vertical page increment size for the vertical scrollbar of a perfedit window.
- void progress_bar_colored (bool flag)

  'Setter' function for member m_progress_bar_colored
- void progress_bar_thick (bool flag)

  'Setter' function for member m_progress_bar_thick
- void window_redraw_rate (int ms)

  'Setter' function for member m_window_redraw_rate_ms
- void midi_ppqn (int ppqn)

  'Setter' function for member m_midi_ppqn This value can be set from 96 to 19200 (this upper limit will be determined by what Sequencer64 can actually handle).
- void midi_buss_override (char buss)

  'Setter' function for member m_midi_buss_override This value can be set from 0 to 31.

Protected Member Functions

- void grid_brackets (int thickness)

  'Getter' function for member m_grid_brackets
- void grid_style (int gridstyle)

  'Setter' function for member m_grid_style
- void mainwnd_rows (int value)

  'Setter' function for member m_mainwnd_rows This value is not modified unless the value parameter is between 4 and 8, inclusive.
- void mainwnd_cols (int value)

  'Setter' function for member m_mainwnd_cols This value is not modified unless the value parameter is between 8 and 10, inclusive.
- void max_sets (int value)

  'Setter' function for member m_max_sets This value is not modified unless the value parameter is between 32 and 64, inclusive.
- void text_x (int value)

  'Setter' function for member m_text_x This value is not modified unless the value parameter is between 6 and 6, inclusive.
- void text_y (int value)

  'Setter' function for member m_text_y This value is not modified unless the value parameter is between 12 and 12, inclusive.
- void seqchars_x (int value)

  'Setter' function for member m_seqchars_x This affects the size or crampiness of a pattern slot, and for now we will hardwire it to 15.
- void seqchars_y (int value)

  'Setter' function for member m_seqchars_y This affects the size or crampiness of a pattern slot, and for now we will hardwire it to 5.
- void seqarea_x (int value)

  'Setter' function for member m_seqarea_x
- void seqarea_y (int value)

  'Setter' function for member m_seqarea_y
- void seqarea_seq_x (int value)

  'Setter' function for member m_seqarea_seq_x
- void seqarea_seq_y (int value)

  'Setter' function for member m_seqarea_seq_y

- void mainwid_border (int value)

  'Setter' function for member m_mainwid_border This value is not modified unless the value parameter is between 0 and 3, inclusive.
- void mainwid_spacing (int value)

  'Setter' function for member m_mainwid_spacing This value is not modified unless the value parameter is between 2 and 6, inclusive.
- void control_height (int value)

  'Setter' function for member m_control_height This value is not modified unless the value parameter is between 0 and 4, inclusive.
- void dump_summary ()

  Provides a debug dump of basic information to help debug a surprisingly intractable problem with all busses having the name and values of the last buss in the configuration.
- void midi_beats_per_bar (int beatsperbar)

  'Setter' function for member m_midi_beats_per_measure This value can be set from 1 to 16.
- void midi_beats_per_minute (int beatsperminute)

  'Setter' function for member m_midi_beats_minute This value can be set from 20 to 500.
- void midi_beat_width (int beatwidth)

  'Setter' function for member m_midi_beatwidth This value can be set to any power of 2 in the range from 1 to 16.

Private Types

- typedef std::vector< user_midi_bus > Busses

  [user-midi-bus-definitions]
- typedef std::vector< user_midi_bus >::iterator BussIterator
- typedef std::vector< user_midi_bus >::const_iterator BussConstIterator
- typedef std::vector< user_instrument > Instruments

  [user-instrument-definitions]
- typedef std::vector< user_instrument >::iterator InstrumentIterator
- typedef std::vector< user_instrument >::const_iterator InstrumentConstIterator

Private Member Functions

- user_midi_bus & private_bus (int buss)

  'Getter' function for member m_midi_buses[index] (internal function) If the index is out of range, then an invalid object is returned.
- user_instrument & private_instrument (int instrum)

  'Getter' function for member m_instruments[index] If the index is out of range, then a invalid object is returned.

Private Attributes

- Busses m_midi_buses

  Provides data about the MIDI busses, readable from the "user" configuration file.
- Instruments m_instruments

  Provides data about the MIDI instruments, readable from the "user" configuration file.
- mainwid_grid_style_t m_grid_style

  [user-interface-settings]
- int m_grid_brackets

  Specify drawing brackets (like the old Seq24) or a solid box.
- int m_mainwnd_rows

  Number of rows in the Patterns Panel.

- int m_mainwnd_cols

  Number of columns in the Patterns Panel.
- int m_max_sets

  Maximum number of screen sets that can be supported.
- int m_mainwid_border

  These control sizes.
- int m_mainwid_spacing
- int m_control_height

  This constants seems to be created for a future purpose, perhaps to reserve space for a new bar on the mainwid pane.
- int m_current_zoom

  Provides the initial zoom value, in units of ticks per pixel.
- bool m_global_seq_feature_save

  If true, this value provide a bit of backward-compatibility with the global key/scale/background-sequence persistence feature.
- int m_seqedit_scale

  Replaces seqedit::m_initial_scale as the repository for the scale to apply when a sequence is loaded into the sequence editor.
- int m_seqedit_key

  Replaces seqedit::m_initial_key as the repository for the key to apply when a sequence is loaded into the sequence editor.
- int m_seqedit_bgsequence

  Replaces seqedit::m_initial_sequence as the repository for the background sequence to apply when a sequence is loaded into the sequence editor.
- bool m_use_new_font

  Sets the usage of the font.
- bool m_allow_two_perfedits

  Enables the usage of two perfedit windows, for added convenience in editing multi-set songs.
- int m_h_perf_page_increment

  Allows a changed to the page size for the horizontal scroll bar.
- int m_v_perf_page_increment

  Allows a changed to the page size for the vertical scroll bar.
- bool m_progress_bar_colored

  If set, makes progress bars have the "progress_color()", instead of black.
- bool m_progress_bar_thick

  If set, makes progress bars thicker than 1 pixel...
- int m_window_redraw_rate_ms

  Provides the global setting for redraw rate of windows.
- int m_text_x

  Constants for the mainwid class.
- int m_text_y
- int m_seqchars_x

  Constants for the mainwid class.
- int m_seqchars_y
- int m_midi_ppqn

  Provides the universal PPQN setting for the duration of this setting.
- int m_midi_beats_per_measure

  Provides the universal and unambiguous MIDI value for beats per measure, also called "beats per bar" (BPB).
- int m_midi_beats_per_minute

  Provides the universal and unambiguous MIDI value for beats per minute (BPM).
- int m_midi_beat_width

  Provides the universal MIDI value for beats width (BW).

- char m_midi_buss_override

  Provides a universal override of the buss number for all sequences, for the purpose of convenience of of testing.
- int m_total_seqs
- int m_seqs_in_set

  Number of patterns/sequences in the Patterns Panel, also known as a "set" or "screen set".
- int m_gmute_tracks

  Number of group-mute tracks that can be supported, which is m_seqs_in_set squared, or 1024.
- int m_max_sequence

  The maximum number of patterns supported is given by the number of patterns supported in the panel (32) times the maximum number of sets (32), or 1024 patterns.
- int m_seqarea_x

  The m_seqarea_x and m_seqarea_y constants are derived from the width and heights of the default character set, and the number of characters in width, and the number of lines, in a pattern/sequence box.
- int m_seqarea_y
- int m_seqarea_seq_x

  Area of what? Doesn't look at all like it is based on the size of characters.
- int m_seqarea_seq_y
- int m_mainwid_x

  The width of the main pattern/sequence grid, in pixels.
- int m_mainwid_y
- bool m_save_user_config

  Provides a temporary variable that can be set from the command line to cause the "user" state to be saved into the "user" configuration file.
- const int mc_min_zoom

  Provides the minimum zoom value, currently a constant.
- const int mc_max_zoom

  Provides the maximum zoom value, currently a constant.
- const int mc_baseline_ppqn

  Permanent storage for the baseline, default PPQN used by Seq24.

Friends

- class userfile

12.73.1 Detailed Description

These settings will eventually be made part of the "user" settings file.

12.73.2 Member Typedef Documentation

12.73.2.1 typedef std::vector<user_midi_bus> seq64::user_settings::Busses [private]

Internal type for the container of user_midi_bus objects. Sorry about the "confusion" about "bus" versus "buss". See Google for arguments about it.

12.73.2.2 typedef std::vector<user_midi_bus>::iterator seq64::user_settings::BussIterator [private]

12.73.2.3 typedef std::vector<user_midi_bus>::const_iterator seq64::user_settings::BussConstIterator [private]

12.73.2.4 typedef std::vector<user_instrument> seq64::user_settings::Instruments [private]

Internal type for the container of user_instrument objects.

12.73.2.5 typedef std::vector<user_instrument>::iterator seq64::user_settings::InstrumentIterator [private]

12.73.2.6 typedef std::vector<user_instrument>::const_iterator seq64::user_settings::InstrumentConstIterator [private]

12.73.3 Member Enumeration Documentation

12.73.3.1 enum seq64::user_settings::mainwid_grid_style_t [private]

Enumerator

grid_style_normal Provides a setting to control the overall style of grid-drawing for the pattern slots in mainwid. These values can be specified in the [user-interface-settings] section of the "user" configuration file.

```
The grid background color is the normal background color for the
current GTK theme.  The box is drawn with brackets on either side.
```

grid_style_white The grid background color is white. This style better fits displaying the white-on-black sequence numbers. The box is drawn with brackets on either side.

grid_style_black The grid background color is black.

grid_style_max Marks the end of the list, and is an illegal value.

12.73.4 Constructor & Destructor Documentation

12.73.4.1 seq64::user_settings::user_settings ( )

12.73.4.2 seq64::user_settings::user_settings (const user_settings & *rhs*)

12.73.5 Member Function Documentation

12.73.5.1 user_settings & seq64::user_settings::operator= (const user_settings & *rhs*)

12.73.5.2 void seq64::user_settings::set_defaults ( )

For the m_midi_buses and m_instruments members, this function can only iterate over the current size of the vectors. But the default size is zero!

12.73.5.3 void seq64::user_settings::normalize ( )

12.73.5.4 bool seq64::user_settings::add_bus (const std::string & *alias*)

12.73.5.5 bool seq64::user_settings::add_instrument (const std::string & *instname*)

12.73.5.6 const user_midi_bus& seq64::user_settings::bus (int *index*) [inline]

Cannot append the const specifier.

12.73.5.7 const user_instrument& seq64::user_settings::instrument (int *index*) [inline]

Cannot append the const specifier.

12.73.5.8 int seq64::user_settings::bus_count ( ) const [inline]

12.73.5.9 void seq64::user_settings::set_bus_instrument (int *index,* int *channel,* int *instrum*)

12.73.5.10 int seq64::user_settings::bus_instrument (int *buss,* int *channel*) [inline]

12.73.5.11 const std::string& seq64::user_settings::bus_name (int *buss*) [inline]

12.73.5.12 int seq64::user_settings::instrument_count ( ) const [inline]

12.73.5.13 void seq64::user_settings::set_instrument_controllers (int *index,* int *cc,* const std::string & *ccname,* bool *isactive*)

12.73.5.14 const std::string& seq64::user_settings::instrument_name (int *instrum*) [inline]

12.73.5.15 const std::string& seq64::user_settings::instrument_name (int *buss,* int *channel*) [inline]

12.73.5.16 bool seq64::user_settings::instrument_controller_active (int *instrum,* int *cc*) [inline]

12.73.5.17 bool seq64::user_settings::controller_active (int *buss,* int *channel,* int *cc*) [inline]

It also has a shorter name.

12.73.5.18 const std::string& seq64::user_settings::instrument_controller_name (int *instrum,* int *cc*) [inline]

12.73.5.19 const std::string& seq64::user_settings::controller_name (int *buss,* int *channel,* int *cc*) [inline]

It also has a shorter name.

12.73.5.20 int seq64::user_settings::grid_style ( ) const [inline]

12.73.5.21 bool seq64::user_settings::grid_is_normal ( ) const [inline]

12.73.5.22 bool seq64::user_settings::grid_is_white ( ) const [inline]

12.73.5.23 bool seq64::user_settings::grid_is_black ( ) const [inline]

12.73.5.24 int seq64::user_settings::grid_brackets ( ) const [inline]

12.73.5.25 int seq64::user_settings::mainwnd_rows ( ) const [inline]

12.73.5.26 int seq64::user_settings::mainwnd_cols ( ) const [inline]

12.73.5.27 int seq64::user_settings::seqs_in_set ( ) const [inline]

12.73.5.28 int seq64::user_settings::gmute_tracks ( ) const [inline]

12.73.5.29 int seq64::user_settings::max_sets ( ) const [inline]

12.73.5.30 int seq64::user_settings::max_sequence ( ) const [inline]

12.73.5.31 int seq64::user_settings::text_x ( ) const [inline]

12.73.5.32 int seq64::user_settings::text_y ( ) const [inline]

12.73.5.33 int seq64::user_settings::seqchars_x ( ) const [inline]

12.73.5.34 int seq64::user_settings::seqchars_y ( ) const [inline]

12.73.5.35 int seq64::user_settings::seqarea_x ( ) const [inline]

12.73.5.36 int seq64::user_settings::seqarea_y ( ) const [inline]

12.73.5.37 int seq64::user_settings::seqarea_seq_x ( ) const [inline]

12.73.5.38 int seq64::user_settings::seqarea_seq_y ( ) const [inline]

12.73.5.39 int seq64::user_settings::mainwid_border ( ) const [inline]

12.73.5.40 int seq64::user_settings::mainwid_spacing ( ) const [inline]

12.73.5.41 int seq64::user_settings::mainwid_x ( ) const [inline]

12.73.5.42 int seq64::user_settings::mainwid_y ( ) const [inline]

12.73.5.43 int seq64::user_settings::control_height ( ) const [inline]

12.73.5.44 int seq64::user_settings::zoom ( ) const [inline]

12.73.5.45 void seq64::user_settings::zoom (int *value*)

The default value is 2. Note that 0 is allowed as a special case, which allows the default zoom to be adjusted when the PPQN value is different from the default.

12.73.5.46 bool seq64::user_settings::global_seq_feature ( ) const [inline]

12.73.5.47 void seq64::user_settings::global_seq_feature (bool *flag*) [inline]

12.73.5.48 int seq64::user_settings::seqedit_scale ( ) const [inline]

12.73.5.49 void seq64::user_settings::seqedit_scale (int *scale*) [inline]

12.73.5.50 int seq64::user_settings::seqedit_key ( ) const [inline]

12.73.5.51 void seq64::user_settings::seqedit_key (int *key*) [inline]

12.73.5.52 int seq64::user_settings::seqedit_bgsequence ( ) const [inline]

12.73.5.53 void seq64::user_settings::seqedit_bgsequence (int *seqnum*) [inline]

12.73.5.54 bool seq64::user_settings::use_new_font ( ) const [inline]

12.73.5.55 bool seq64::user_settings::allow_two_perfedits ( ) const [inline]

12.73.5.56 int seq64::user_settings::perf_h_page_increment ( ) const [inline]

12.73.5.57 int seq64::user_settings::perf_v_page_increment ( ) const [inline]

12.73.5.58 bool seq64::user_settings::progress_bar_colored ( ) const [inline]

12.73.5.59 bool seq64::user_settings::progress_bar_thick ( ) const [inline]

12.73.5.60 int seq64::user_settings::window_redraw_rate ( ) const [inline]

12.73.5.61 bool seq64::user_settings::save_user_config ( ) const [inline]

12.73.5.62 void seq64::user_settings::save_user_config (bool *flag*) [inline]

12.73.5.63 void seq64::user_settings::grid_brackets (int *thickness*) [inline], [protected]

12.73.5.64 void seq64::user_settings::grid_style (int *gridstyle*) [protected]

12.73.5.65 void seq64::user_settings::mainwnd_rows (int *value*) [protected]

The default value is 4. Dependent values are recalculated after the assignment.

12.73.5.66 void seq64::user_settings::mainwnd_cols (int *value*) [protected]

The default value is 8. Dependent values are recalculated after the assignment.

12.73.5.67 void seq64::user_settings::max_sets (int *value*) [protected]

The default value is 32. Dependent values are recalculated after the assignment.

12.73.5.68 void seq64::user_settings::text_x (int *value*) [protected]

The default value is 6. Dependent values are recalculated after the assignment. This value is currently restricted, until we can code up a bigger font.

12.73.5.69 void seq64::user_settings::text_y (int *value*) [protected]

The default value is 12. Dependent values are recalculated after the assignment. This value is currently restricted, until we can code up a bigger font.

12.73.5.70 void seq64::user_settings::seqchars_x (int *value*) [protected]

12.73.5.71 void seq64::user_settings::seqchars_y (int *value*) [protected]

12.73.5.72 void seq64::user_settings::seqarea_x (int *value*) [protected]

12.73.5.73 void seq64::user_settings::seqarea_y (int *value*) [protected]

12.73.5.74 void seq64::user_settings::seqarea_seq_x (int *value*) [protected]

12.73.5.75 void seq64::user_settings::seqarea_seq_y (int *value*) [protected]

12.73.5.76 void seq64::user_settings::mainwid_border (int *value*) [protected]

The default value is 0. Dependent values are recalculated after the assignment.

12.73.5.77 void seq64::user_settings::mainwid_spacing (int *value*) [protected]

The default value is 2. Dependent values are recalculated after the assignment.

12.73.5.78 void seq64::user_settings::control_height (int *value*) [protected]

The default value is 0. Dependent values are recalculated after the assignment.

12.73.5.79 void seq64::user_settings::dump_summary ( ) [protected]

Does its work only if PLATFORM_DEBUG and SEQ64_USE_DEBUG_OUTPUT are defined. Only enabled in emergencies :-D.

12.73.5.80 int seq64::user_settings::midi_ppqn ( ) const [inline]

12.73.5.81 int seq64::user_settings::midi_beats_per_bar ( ) const [inline]

12.73.5.82 int seq64::user_settings::midi_beats_per_minute ( ) const [inline]

12.73.5.83 int seq64::user_settings::midi_beat_width ( ) const [inline]

12.73.5.84 char seq64::user_settings::midi_buss_override ( ) const [inline]

12.73.5.85 int seq64::user_settings::min_zoom ( ) const [inline]

12.73.5.86 int seq64::user_settings::max_zoom ( ) const [inline]

12.73.5.87 int seq64::user_settings::baseline_ppqn ( ) const [inline]

12.73.5.88 void seq64::user_settings::use_new_font (bool *flag*) [inline]

12.73.5.89 void seq64::user_settings::allow_two_perfedits (bool *flag*) [inline]

12.73.5.90 void seq64::user_settings::perf_h_page_increment (int *inc*)

This value ranges from 1 (the original value, really too small for a "page" operation) to 6 (which is 24 measures, the same as the typical width of the perfroll)

12.73.5.91 void seq64::user_settings::perf_v_page_increment (int *inc*)

This value ranges from 1 (the original value, really too small for a "page" operation) to 18 (which is 18 tracks, slightly more than the typical height of the perfroll)

12.73.5.92 void seq64::user_settings::progress_bar_colored (bool *flag*) [inline]

12.73.5.93 void seq64::user_settings::progress_bar_thick (bool *flag*) [inline]

12.73.5.94 void seq64::user_settings::window_redraw_rate (int *ms*) [inline]

12.73.5.95 void seq64::user_settings::midi_ppqn (int *value*)

The default value is 192.

12.73.5.96 void seq64::user_settings::midi_buss_override (char *buss*)

The default value is -1, which means that there is no buss override. It provides a way to override the buss number for smallish MIDI files. It replaces the buss-number read from the file. This option is turned on by the –bus option, and is merely a convenience feature for the quick previewing of a tune. (It's called "developer laziness".)

12.73.5.97 void seq64::user_settings::midi_beats_per_bar (int *value*) [protected]

The default value is 4.

12.73.5.98 void seq64::user_settings::midi_beats_per_minute (int *value*) [protected]

The default value is 120.

12.73.5.99 void seq64::user_settings::midi_beat_width (int *bw*) [protected]

The default value is 4.

12.73.5.100 user_midi_bus & seq64::user_settings::private_bus (int *index*) [private]

This invalid object has an empty alias, and all the instrument numbers are -1.

12.73.5.101 user_instrument & seq64::user_settings::private_instrument (int *index*) [private]

This invalid object has an empty(), instrument name, false for all controllers_active[] values, and empty controllers[] string values.

12.73.6 Friends And Related Function Documentation

12.73.6.1 friend class userfile [friend]

12.73.7 Field Documentation

12.73.7.1 Busses seq64::user_settings::m_midi_buses [private]

Since this object is a vector, its size is adjustable.

12.73.7.2 Instruments seq64::user_settings::m_instruments [private]

The size is adjustable, and grows as objects are added.

12.73.7.3 mainwid_grid_style_t seq64::user_settings::m_grid_style [private]

These are not labelled, but are present in the "user" configuration file in the following order:

```
-#  grid-style
-#  grid-brackets
-#  mainwnd-rows
-#  mainwnd-cols
-#  max-set
-#  mainwid-border
-#  control-height
-#  zoom
-#  global-seq-feature
-#  use-new-font
-#  allow-two-perfedits
-#  perf-h-page-increment
-#  perf-v-page-increment
-#  progress-bar-colored (new)
-#  progress-bar-thick (new)
-#  window-redraw-rate-ms (new)
```

Specifies the current grid style.

12.73.7.4 int seq64::user_settings::m_grid_brackets [private]

0 = no brackets, 1 and above is the thickness of the brakcets. 1 is the normal thickness of the brackets, 2 is a two-pixel thickness, and so on.

12.73.7.5 int seq64::user_settings::m_mainwnd_rows [private]

The current value is 4, and if changed, many other values depend on it. Together with m_mainwnd_cols, this value fixes the patterns grid into a 4 x 8 set of patterns known as a "screen set". We would like to be able to change this value from 4 to 8, and maybe allow the values of 5, 6, and 7 as well. But if we could just get 8 working, then well would Sequencer64 deserve the 64 in its name.

12.73.7.6 int seq64::user_settings::m_mainwnd_cols [private]

The current value is 4, and probably won't change, since other values depend on it. Together with m_mainwnd_rows, this value fixes the patterns grid into a 4 x 8 set of patterns known as a "screen set".

12.73.7.7 int seq64::user_settings::m_max_sets [private]

Basically, that the number of times the Patterns Panel can be filled. 32 sets can be created. Although this value is part of the "user" configuration file, it is likely that it will never change. Rather, the number of sequences per set would change. We'll see.

12.73.7.8 int seq64::user_settings::m_mainwid_border [private]

We'll try changing them and see what happens. Increasing these value spreads out the pattern grids a little bit and makes the Patterns panel slightly bigger. Seems like it would be useful to make these values user-configurable.

12.73.7.9 int seq64::user_settings::m_mainwid_spacing [private]

12.73.7.10 int seq64::user_settings::m_control_height [private]

But it is used only in this header file, to define m_mainwid_y, but doesn't add anything to that value.

12.73.7.11 int seq64::user_settings::m_current_zoom [private]

The original default value was 32 ticks per pixel, but larger PPQN values need higher values, and we will have to adapt the default zoom to the PPQN value. Also, the zoom can never be zero, as it can appear as the divisor in scaling equations.

12.73.7.12 bool seq64::user_settings::m_global_seq_feature_save [private]

In this feature, applying one of these three changes to a sequence causes them to also be applied to sequences that are subsequently opened for editing. However, we improve on this feature by allowing the changes to be saved in the global, proprietary part of the saved MIDI file.

If false, the user can still save the key/scale/background-sequence values with each individual sequence, so they can be different.

This value will be true by default, unless changed in the "user" configuration file.

12.73.7.13 int seq64::user_settings::m_seqedit_scale [private]

Its default value is c_scale_off. Although this value is now stored in the user_settings class, it always comes from the currently loaded MIDI file, if present. If m_global_seq_feature_save is true, this variable is stored in the "proprietary" track at the end of the file, under the control tag c_musicscale, and will be applied to any sequence that is edited. If m_global_seq_feature_save is false, this variable is stored, if used, in the meta-data for the sequence to which it applies, and, again, is tagged with the control tag c_musicscale.

12.73.7.14 int seq64::user_settings::m_seqedit_key [private]

Its default value is SEQ64_KEY_OF_C. Although this value is now stored in the user_settings class, it always comes from the currently loaded MIDI file, if present. If m_global_seq_feature_save is true, this variable is stored in the "proprietary" track at the end of the file, under the control tag c_musickey, and will be applied to any sequence that is edited. If m_global_seq_feature_save is false, this variable is stored, if used, in the meta-data for the sequence to which it applies, and, again, is tagged with the control tag c_musickey.

12.73.7.15 int seq64::user_settings::m_seqedit_bgsequence [private]

Its default value is SEQ64_SEQUENCE_LIMIT. Although this value is now stored in the user_settings class, it always comes from the currently loaded MIDI file, if present. If m_global_seq_feature_save is true, this variable is stored, if it has a valid (but not "legal") value, in the "proprietary" track at the end of the file, under the control tag c_backsequence, and will be applied to any sequence that is edited. If m_global_seq_feature_save is false, this variable is stored, if used, in the meta-data for the sequence to which it applies, and, again, is tagged with the control tag c_backsequence.

12.73.7.16 bool seq64::user_settings::m_use_new_font [private]

By default, in normal mode, the new font is used. In legacy mode, the old font is used.

12.73.7.17 bool seq64::user_settings::m_allow_two_perfedits [private]

Defaults to true.

12.73.7.18 int seq64::user_settings::m_h_perf_page_increment [private]

The value used to be hardwired to 1 (in four-measure units), now it defaults to 4 (16 measures at a time). The value of 1 is already covered by the scrollbar arrows.

12.73.7.19 int seq64::user_settings::m_v_perf_page_increment [private]

The value used to be hardwired to 1 (in single-track units), now it defaults to 8. The value of 1 is already covered by the scrollbar arrows.

12.73.7.20 bool seq64::user_settings::m_progress_bar_colored [private]

This value is hardwired in the gui_palette_gtk2 module, to red. Really, that is the only color that stands out as well as black.

12.73.7.21 bool seq64::user_settings::m_progress_bar_thick [private]

2 pixels. It isn't useful to support anything thicker.

12.73.7.22 int seq64::user_settings::m_window_redraw_rate_ms [private]

Not all windows use this yet. The default is 40 ms (c_redraw_ms, which is 20 ms in Windows builds)), but some windows originally used 25 ms, so beware of side-effects.

12.73.7.23 int seq64::user_settings::m_text_x [private]

The m_text_x and m_text_y constants help define the "seqarea" size. It looks like these two values are the character width (x) and height (y) in pixels. Thus, these values would be dependent on the font chosen. But that, currently, is hard-wired. See the m_font_6_12[] array for the default font specification.

However, please not that font files are not used. Instead, the fonts are provided by two pixmaps in the `src/pixmap` directory: `font_b.xpm` (black lettering on a white background) and `font_w.xpm` (white lettering on a black background).

We have added black-on-yellow and yellow-on-black versions of the fonts, to support the highlighting of pattern boxes if they are empty of actual MIDI events.

We have also added a set of four new font files that are roughly the same size, and are treated as the same size, but look smooth and less like a DOS-era font.

The font module does not use these values directly, but does define some similar variables that differ slightly between the two styles of font. There are a lot of tricks and hard-wired places to fix before further work can be done with fonts in Sequencer64.

12.73.7.24 int seq64::user_settings::m_text_y [private]

12.73.7.25 int seq64::user_settings::m_seqchars_x [private]

The m_seqchars_x and m_seqchars_y constants help define the "seqarea" size. These look like the number of characters per line and the number of lines of characters, in a pattern/sequence box.

12.73.7.26 int seq64::user_settings::m_seqchars_y [private]

12.73.7.27 int seq64::user_settings::m_midi_ppqn [private]

This variable replaces the global ppqn. The default value of this setting is 192 parts-per-quarter-note (PPQN). There is still a lot of work to get a different PPQN to work properly in speed of playback, scaling of the user interface, and other issues. Note that this value can be changed by the still-experimental –ppqn option. There is one remaining trace of the global, though: DEFAULT_PPQN.

12.73.7.28 int seq64::user_settings::m_midi_beats_per_measure [private]

This variable will replace the global beats per measure. The default value of this variable is SEQ64_DEFAULT_↩ BEATS_PER_MEASURE (4). For external access, we will call this value "beats per bar", abbreviate it "BPB", and use "bpb" in any accessor function names. Now, although it applies to the whole session, we should be able to continue seq24's tradition of allowing each sequence to have its own time signature. Also, there are a number of places where the number 4 appears and looks like it might be a hardwired BPB value, either for MIDI purposes or for drawing the piano-roll grids. So we might need a couple different versions of this variable.

12.73.7.29 int seq64::user_settings::m_midi_beats_per_minute [private]

This variable will replace the global beats per minute. The default value of this variable is DEFAULT_BPM (120). This variable should apply to the whole session; there's probably no way to support a diffent tempo for each sequence. But we shall see. For external access, we will call this value "beats per minute", abbreviate it "BPM", and use "bpm" in any accessor function names.

12.73.7.30 int seq64::user_settings::m_midi_beat_width [private]

This variable will replace the global beat_width. The default value of this variable is DEFAULT_BEAT_WIDTH (4). Now, although it applies to the whole session, we should be able to continue seq24's tradition of allowing each sequence to have its own time signature. Also, there are a number of places where the number 4 appears and looks like it might be a hardwired BW value, either for MIDI purposes or for drawing the user-interface. So we might need a couple different versions of this variable. For external access, we will call this value "beat width", abbreviate it "BW", and use "bw" in any accessor function names.

12.73.7.31 char seq64::user_settings::m_midi_buss_override [private]

This variable replaces the global buss-override variable, and is set via the command-line option –bus.

12.73.7.32 int seq64::user_settings::m_total_seqs [private]

12.73.7.33 int seq64::user_settings::m_seqs_in_set [private]

This value is 4 x 8 = 32 by default.

Warning

Currently implicit/explicit in a number of the "rc" file and rc_settings. Would probably want the left 32 or the first 32 items in the main window only to be subject to keystroke control. This value is calculated by the normalize() function, and is *not* part of the "user" configuration file.

12.73.7.34 int seq64::user_settings::m_gmute_tracks [private]

This value is *not* part of the "user" configuration file; it is calculated by the normalize() function.

12.73.7.35 int seq64::user_settings::m_max_sequence [private]

It is a derived value, and not stored in the "user" file.

```
m_max_sequence = m_seqs_in_set * m_max_sets;
```

12.73.7.36 int seq64::user_settings::m_seqarea_x [private]

Compare these two constants to m_seqarea_seq_x(y), which was in mainwid.h, but is now in this file.

12.73.7.37 int seq64::user_settings::m_seqarea_y [private]

12.73.7.38 int seq64::user_settings::m_seqarea_seq_x [private]

These are used only in the mainwid module.

12.73.7.39 int seq64::user_settings::m_seqarea_seq_y [private]

12.73.7.40 int seq64::user_settings::m_mainwid_x [private]

Affected by the m_mainwid_border and m_mainwid_spacing values.

```
c_mainwid_x =
(
    (c_seqarea_x + c_mainwid_spacing) * c_mainwnd_cols -
        c_mainwid_spacing + c_mainwid_border * 2
);
```

12.73.7.41 int seq64::user_settings::m_mainwid_y [private]

12.73.7.42 bool seq64::user_settings::m_save_user_config [private]

Normally, this state is not saved. It is not saved because there is currently no user-interface for editing it, and because it can pick up some command-line options, and it is not right to have them written to the "user" configuration file.

(The "rc" configuration file is a different case, having historically always been saved, and having a number of command-line options, such as JACK settings that should generally be permanent on a given system.)

Anyway, this flag can be set by the –user-save option. This setting is never saved. But note that, if no "user" configuration file is found, it is then saved anyway.

12.73.7.43 const int seq64::user_settings::mc_min_zoom [private]

It's value is 1.

12.73.7.44 const int seq64::user_settings::mc_max_zoom [private]

It's value was 32, but is now 512, to allow for better presentation of high PPQN valued sequences.

12.73.7.45 const int seq64::user_settings::mc_baseline_ppqn [private]

This value is necessary in order to keep user-interface elements stable when different PPQNs are used. It is set to DEFAULT_PPQN.

12.74 seq64::userfile Class Reference

Supports the user's ~/.config/sequencer64/sequencer64.usr and ~/.seq24usr configuration file.

Inheritance diagram for seq64::userfile:



Public Member Functions

- userfile (const std::string &a_name)

  Principal constructor.
- ~userfile ()

  A rote destructor needed for a derived class.
- bool parse (perform &a_perf)

  Parses a "usr" file, filling in the given perform object.
- bool write (const perform &a_perf)

  This function just returns false, as there is no "perform" information in the user-file yet.

Private Member Functions

- void dump_setting_summary ()

  Provides a debug dump of basic information to help debug a surprisingly intractable problem with all busses having the name and values of the last buss in the configuration.

Additional Inherited Members

12.74.1 Constructor & Destructor Documentation

12.74.1.1 seq64::userfile::userfile (const std::string & *name*)

Parameters

name	Provides the full file path specification to the configuration file.

12.74.1.2 seq64::userfile::~userfile ( )

12.74.2 Member Function Documentation

12.74.2.1 bool seq64::userfile::parse (perform & *a_perf*) [virtual]

This function opens the file as a text file (line-oriented).

Parameters

a_perf	The performance object, currently unused.

Returns

Returns true if the parsing succeeded.

Implements seq64::configfile.

12.74.2.2 bool seq64::userfile::write (const perform & *a_perf*) [virtual]

Parameters

a_perf	The performance object, currently unused.

Returns

Returns true if the writing succeeded.

Implements seq64::configfile.

12.74.2.3 void seq64::userfile::dump_setting_summary ( ) [private]

Does work only if PLATFORM_DEBUG is defined; see the user_settings class.

Index