Sequencer64 Developer Reference Manual 0.9.19

Generated by Doxygen 1.8.12

Contents

1	Seq	uencer6	64		1
	1.1	Introdu	uction		1
2	MID	l File Pa	ırsing in S	Sequencer64	3
	2.1	Introdu	uction		3
	2.2	SMF 1	Parsing .		3
		2.2.1	MIDI File	Header, MThd	3
		2.2.2	MIDI Tra	ck, MTrk	4
			2.2.2.1	Channel Events	4
			2.2.2.2	Meta Events	5
		2.2.3	Meta Eve	ents Summary	6
			2.2.3.1	Sequence Number (0x00)	6
			2.2.3.2	Track/Sequence Name (0x03)	7
			2.2.3.3	End of Track (0x2F)	7
			2.2.3.4	Set Tempo Event (0x51)	7
			2.2.3.5	Time Signature Event (0x58)	8
			2.2.3.6	SysEx Event (0xF0)	9
			2.2.3.7	Sequencer Specific (0x7F)	10
			2.2.3.8	Non-Specific End of Sequence	10
	2.3	SMF 0	Parsing .		10
	24	Runnir	na Status		11

ii CONTENTS

3	JAC	CK, Live, and Song Modes in Sequencer64					
	3.1	Introduction					
	3.2	JACK Functions	13				
		3.2.1 jack_client_open()	14				
		3.2.2 jack_on_shutdown()	14				
		3.2.3 jack_set_sync_callback()	14				
		3.2.4 jack_set_process_callback()	15				
		3.2.5 jack_set_session_callback()	15				
		3.2.6 jack_activate()	15				
		3.2.7 jack_release_timebase()	15				
		3.2.8 jack_client_close()	15				
		3.2.9 jack_transport_start()	15				
		3.2.10 jack_transport_stop()	15				
		3.2.11 jack_transport_locate()	15				
		3.2.12 jack_transport_reposition()	16				
		3.2.13 jack_transport_query()	16				
	3.3	Modes Operation	16				
		3.3.1 No JACK, Live Mode	16				
		3.3.2 No JACK, Song Mode	16				
		3.3.3 JACK Transport	17				
	3.4	Breakage					
	3.5	JACK References	18				
4	Heer						
•	4.1	r Testing of Sequencer64 with Yoshimi Introduction	19 19				
	4.1	Smoke Test	19				
	4.3	Tests in the Patterns Window	20				
		4.3.1 Button Clicks on a Pattern	21				
		· · · · · · · · · · · · · · · · · · ·					
	4.4	4.3.3 The Sequencer64 User File	21				
	4.4	Tests Using Valgrind	21				
		4.4.1 Valgrind Suppressions	22				
		4.4.2 Full Valgrind Leak-Checking	22				
		4.4.2.1 Leak-Checking Basic Operation	23				
	4.5	Specific Fault Debugging	23				
	4.6	Snipping of a MIDI file.	23				

5	Lice	enses	25
	5.1	License Terms for the This Project.	25
	5.2	XPC Application License	25
	5.3	XPC Library License	26
	5.4	XPC Documentation License	26
	5.5	XPC Affero License	27
	5.6	XPC License Summary	27
6	Todo	o List	29
7	Depi	recated List	31
8	Nam	nespace Index	33
	8.1	Namespace List	33
9	Hiera	archical Index	35
	9.1	Class Hierarchy	35
10	Data	a Structure Index	37
	10.1	Data Structures	37
11		nespace Documentation	41
		Gtk Namespace Reference	41
	11.2	seq64 Namespace Reference	41
		11.2.1 Detailed Description	53
		11.2.2 Typedef Documentation	53
		11.2.2.1 midibyte	53
		11.2.2.2 bussbyte	53
		11.2.2.3 midishort	53
		11.2.2.4 midilong	54
		11.2.2.5 midipulse	54
		11.2.3 Enumeration Type Documentation	54
		11.2.3.1 wave_type_t	54
		11.2.3.2 seq_modifier_t	54

iv CONTENTS

	11.2.3.3	seq_event_type_t	55
	11.2.3.4	seq_scroll_direction_t	55
	11.2.3.5	clock_e	56
	11.2.3.6	interaction_method_t	56
	11.2.3.7	c_music_scales	56
	11.2.3.8	draw_type_t	57
	11.2.3.9	mouse_action_e	57
	11.2.3.10	edit_action_t	57
11.2.4	Function	Documentation	58
	11.2.4.1	extract_timing_numbers()	58
	11.2.4.2	pulses_to_string()	59
	11.2.4.3	pulses_to_measurestring()	59
	11.2.4.4	pulses_to_midi_measures()	59
	11.2.4.5	pulses_to_timestring() [1/2]	60
	11.2.4.6	pulses_to_timestring() [2/2]	60
	11.2.4.7	measurestring_to_pulses()	61
	11.2.4.8	midi_measures_to_pulses()	61
	11.2.4.9	timestring_to_pulses()	62
	11.2.4.10	string_to_pulses()	62
	11.2.4.11	string_to_midibyte()	62
	11.2.4.12	shorten_file_spec()	64
	11.2.4.13	string_not_void()	64
	11.2.4.14	string_is_void()	65
	11.2.4.15	strings_match()	65
	11.2.4.16	log2_time_sig_value()	65
	11.2.4.17	tempo_us_to_bytes()	66
	11.2.4.18	zoom_power_of_2()	66
	11.2.4.19	beats_per_minute_from_tempo_us()	66
	11.2.4.20	tempo_us_from_beats_per_minute()	67
	11.2.4.21	tempo_to_us()	67

11.2.4.22 pulse_length_us()	67
11.2.4.23 delta_time_us_to_ticks()	8
11.2.4.24 ticks_to_delta_time_us()	8
11.2.4.25 clock_tick_duration_bogus()	69
11.2.4.26 clock_ticks_from_ppqn()	39
11.2.4.27 double_ticks_from_ppqn()	70
11.2.4.28 pulses_per_measure()	70
11.2.4.29 measures_to_ticks()	70
11.2.4.30 wave_func()	71
11.2.4.31 help_check()	71
11.2.4.32 parse_options_files()	72
11.2.4.33 parse_command_line_options()	72
11.2.4.34 write_options_files()	73
11.2.4.35 build_details()	73
11.2.4.36 to_string()	73
11.2.4.37 file_access()	74
11.2.4.38 file_exists()	74
11.2.4.39 file_readable()	74
11.2.4.40 file_writable()	74
11.2.4.41 file_accessible()	75
11.2.4.42 file_executable()	75
11.2.4.43 file_is_directory()	75
11.2.4.44 make_directory()	76
11.2.4.45 ppqn_is_valid()	76
11.2.4.46 jack_sync_callback()	76
11.2.4.47 jack_shutdown_callback()	77
11.2.4.48 jack_timebase_callback()	77
11.2.4.49 jack_process_callback()	78
11.2.4.50 get_current_jack_position()	78
11.2.4.51 jack_session_callback()	78

vi

	11.2.4.52	2 invalid_key()	٠.	 . /
	11.2.4.53	3 keyval_name()		 . 7
	11.2.4.54	4 keyval_normalize()		 . 7
	11.2.4.55	5 create_lash_driver()		 . 7
	11.2.4.56	6 lash_driver()		 . 8
	11.2.4.57	7 delete_lash_driver()		 . 8
	11.2.4.58	3 is_null_midipulse()		 . 8
	11.2.4.59	9 output_thread_func()		 . 8
	11.2.4.60	D input_thread_func()		 . 8
	11.2.4.61	1 rc()		 . 8
	11.2.4.62	2 usr()		 . 8
	11.2.4.63	3 choose_ppqn()		 . 8
	11.2.4.64	4 min()		 . 8
	11.2.4.65	5 make_section_name()		 . 8
	11.2.4.66	6 font_render()		 . 8
	11.2.4.67	7 adjustment_dummy()		 . 8
	11.2.4.68	B update_mainwid_sequences()		 . 8
	11.2.4.69	9 update_perfedit_sequences()		 . 8
	11.2.4.70	FF_RW_timeout()		 . 8
	11.2.4.71	1 clamp() [1/2]		 . 8
	11.2.4.72	2 clamp() [2/2]		 . 8
11.2.5	Variable D	Documentation		 . 8
	11.2.5.1	c_controller_names		 . 8
	11.2.5.2	EVENT_STATUS_BIT		 . 8
	11.2.5.3	EVENT_ANY		 . 8
	11.2.5.4	EVENT_NOTE_OFF		 . 8
	11.2.5.5	EVENT_NOTE_ON		 . 8
	11.2.5.6	EVENT_AFTERTOUCH		 . 8
	11.2.5.7	EVENT_CONTROL_CHANGE		 . 8
	11.2.5.8	EVENT_PROGRAM_CHANGE		 . 8

CONTENTS vii

11.2.5.9 EVENT_CHANNEL_PRESSURE	85
11.2.5.10 EVENT_PITCH_WHEEL	85
11.2.5.11 EVENT_MIDI_SYSEX	85
11.2.5.12 EVENT_MIDI_QUARTER_FRAME	85
11.2.5.13 EVENT_MIDI_SONG_POS	85
11.2.5.14 EVENT_MIDI_SONG_SELECT	86
11.2.5.15 EVENT_MIDI_SONG_F4	86
11.2.5.16 EVENT_MIDI_SONG_F5	86
11.2.5.17 EVENT_MIDI_TUNE_SELECT	86
11.2.5.18 EVENT_MIDI_SYSEX_END	86
11.2.5.19 EVENT_MIDI_SYSEX_CONTINUE	86
11.2.5.20 EVENT_MIDI_CLOCK	86
11.2.5.21 EVENT_MIDI_SONG_F9	86
11.2.5.22 EVENT_MIDI_START	86
11.2.5.23 EVENT_MIDI_CONTINUE	86
11.2.5.24 EVENT_MIDI_STOP	87
11.2.5.25 EVENT_MIDI_SONG_FD	87
11.2.5.26 EVENT_MIDI_ACTIVE_SENS	87
11.2.5.27 EVENT_MIDI_RESET	87
11.2.5.28 EVENT_MIDI_META	87
11.2.5.29 EVENT_NULL_CHANNEL	87
11.2.5.30 EVENT_GET_CHAN_MASK	87
11.2.5.31 EVENT_CLEAR_CHAN_MASK	87
11.2.5.32 EVENTS_ALL	87
11.2.5.33 EVENTS_UNSELECTED	88
11.2.5.34 c_midibus_output_size	88
11.2.5.35 c_midibus_input_size	88
11.2.5.36 c_midibus_sysex_chunk	88
11.2.5.37 c_midibus	88
11.2.5.38 c_midich	89

viii CONTENTS

11.2.5.39 c_midiclocks
11.2.5.40 c_triggers
11.2.5.41 c_notes
11.2.5.42 c_timesig
11.2.5.43 c_bpmtag
11.2.5.44 c_triggers_new
11.2.5.45 c_mutegroups
11.2.5.46 c_midictrl
11.2.5.47 c_musickey
11.2.5.48 c_musicscale
11.2.5.49 c_backsequence
11.2.5.50 c_transpose
11.2.5.51 c_perf_bp_mes
11.2.5.52 c_perf_bw
11.2.5.53 c_midi_track_ctrl
11.2.5.54 c_midi_control_bpm_up
11.2.5.55 c_midi_control_bpm_dn
11.2.5.56 c_midi_control_ss_up
11.2.5.57 c_midi_control_ss_dn
11.2.5.58 c_midi_control_mod_replace
11.2.5.59 c_midi_control_mod_snapshot
11.2.5.60 c_midi_control_mod_queue
11.2.5.61 c_midi_control_mod_gmute
11.2.5.62 c_midi_control_mod_glearn
11.2.5.63 c_midi_control_play_ss
11.2.5.64 c_midi_controls
11.2.5.65 c_scales_policy
11.2.5.66 c_scales_transpose_up
11.2.5.67 c_scales_transpose_dn
11.2.5.68 c_scales_text

11.2.5.69 c_key_text
11.2.5.70 c_interval_text
11.2.5.71 c_chord_text
11.2.5.72 c_chord_number
11.2.5.73 c_chord_table_text
11.2.5.74 c_chord_size
11.2.5.75 c_chord_table
11.2.5.76 c_max_instruments
11.2.5.77 c_max_busses
11.2.5.78 versiontext
11.2.5.79 long_options
11.2.5.80 s_arg_list
11.2.5.81 s_help_1a
11.2.5.82 s_help_1b
11.2.5.83 s_help_2
11.2.5.84 s_help_3
11.2.5.85 s_help_4
11.2.5.86 s_build_highlight_empty
11.2.5.87 s_build_lash_support
11.2.5.88 s_build_jack_support
11.2.5.89 s_build_jack_session
11.2.5.90 s_event_editor
11.2.5.91 s_build_pause_support
11.2.5.92 s_build_use_event_map
11.2.5.93 s_build_chord_generator
11.2.5.94 s_build_edit_highlight
11.2.5.95 s_build_timesig_tempo
11.2.5.96 s_build_midi_vector
11.2.5.97 s_build_solid_grid
11.2.5.98 s_build_follow_progress

11.2.5.99 s_statistics_support)7
11.2.5.100s_strip_empty_mutes	97
11.2.5.101s_seq32_jack_support)7
11.2.5.102s_seq32_transport	97
11.2.5.103s_seq32_transpose	98
11.2.5.104s_seq32_menu_buttons	98
11.2.5.105s_character_mapping	98
11.2.5.106s_global_lash_driver	98
11.2.5.107c_status_replace	98
11.2.5.10&_status_snapshot	98
11.2.5.10%_status_queue	98
11.2.5.110g_rc_settings	98
11.2.5.111g_user_settings	99
11.2.5.112s_handlesize [1/2]	99
11.2.5.113s_jitter_amount	99
11.2.5.114gs_mainwid_pointer	99
11.2.5.115c_mainwid_x	99
11.2.5.116c_mainwid_y	99
11.2.5.117gs_perfedit_pointer_0	99
11.2.5.118gs_perfedit_pointer_1	99
11.2.5.119s_handlesize [2/2]	99

CONTENTS xi

12	Data	Structu	ure Documentation	101
	12.1	seq64:	:AbstractPerfInput Class Reference	101
		12.1.1	Constructor & Destructor Documentation	102
			12.1.1.1 AbstractPerfInput()	102
			12.1.1.2 ~AbstractPerfInput()	102
		12.1.2	Member Function Documentation	103
			12.1.2.1 on_button_press_event()	103
			12.1.2.2 on_button_release_event()	103
			12.1.2.3 on_motion_notify_event()	103
			12.1.2.4 activate_adding()	103
			12.1.2.5 handle_motion_key()	103
			12.1.2.6 is_adding()	103
			12.1.2.7 set_adding()	104
			12.1.2.8 is_adding_pressed()	104
			12.1.2.9 set_adding_pressed()	104
		12.1.3	Friends And Related Function Documentation	104
			12.1.3.1 perfroll	104
		12.1.4	Field Documentation	104
			12.1.4.1 m_adding	104
			12.1.4.2 m_adding_pressed	104
	12.2	seq64:	:automutex Class Reference	104
		12.2.1	Detailed Description	105
		12.2.2	Constructor & Destructor Documentation	105
			12.2.2.1 automutex() [1/3]	105
			12.2.2.2 automutex() [2/3]	105
			12.2.2.3 automutex() [3/3]	105
			12.2.2.4 ~automutex()	105
		12.2.3	Member Function Documentation	105
			12.2.3.1 operator=()	106
		12.2.4	Field Documentation	106

xii CONTENTS

	12.2.4.1 m_safety_mutex)6
12.3 seq64:	click Class Reference)6
12.3.1	Detailed Description)7
12.3.2	Constructor & Destructor Documentation)7
	12.3.2.1 click() [1/3])7
	12.3.2.2 click() [2/3])7
	12.3.2.3 click() [3/3])8
12.3.3	Member Function Documentation)8
	12.3.3.1 operator=())8
	12.3.3.2 is_press())8
	12.3.3.3 is_left())8
	12.3.3.4 is_middle())8
	12.3.3.5 is_right())8
	12.3.3.6 x())9
	12.3.3.7 y())9
	12.3.3.8 button())9
	12.3.3.9 modifier())9
	12.3.3.10 mod_control())9
	12.3.3.11 mod_control_shift())9
	12.3.3.12 mod_super())9
12.3.4	Field Documentation)9
	12.3.4.1 m_is_press)9
	12.3.4.2 m_x)9
	12.3.4.3 m_y	0
	12.3.4.4 m_button	0
	12.3.4.5 m_modifier	0
12.4 seq64:	condition_var Class Reference	0
12.4.1	Detailed Description	1
12.4.2	Constructor & Destructor Documentation	1
	12.4.2.1 condition_var()	1

CONTENTS xiii

	12.4.3	Member Function Documentation
		12.4.3.1 wait()
		12.4.3.2 signal()
	12.4.4	Field Documentation
		12.4.4.1 sm_cond
		12.4.4.2 m_cond
12.5	seq64:	configfile Class Reference
	12.5.1	Constructor & Destructor Documentation
		12.5.1.1 configfile()
		12.5.1.2 ~configfile()
	12.5.2	Member Function Documentation
		12.5.2.1 next_data_line()
		12.5.2.2 line_after()
		12.5.2.3 parse()
		12.5.2.4 write()
	12.5.3	Field Documentation
		12.5.3.1 m_name
		12.5.3.2 m_d
		12.5.3.3 m_line
12.6	seq64:	:editable_event Class Reference
	12.6.1	Detailed Description
	12.6.2	Member Enumeration Documentation
		12.6.2.1 category_t
		12.6.2.2 timestamp_format_t
	12.6.3	Constructor & Destructor Documentation
		12.6.3.1 editable_event() [1/4]
		12.6.3.2 editable_event() [2/4]
		12.6.3.3 editable_event() [3/4]
		12.6.3.4 editable_event() [4/4]
		12.6.3.5 ~editable_event()

xiv CONTENTS

12.6.4	Member Function Documentation	121
	12.6.4.1 value_to_name()	121
	12.6.4.2 name_to_value()	122
	12.6.4.3 operator=()	122
	12.6.4.4 parent()	122
	12.6.4.5 category() [1/3]	122
	12.6.4.6 category() [2/3]	122
	12.6.4.7 category_string()	123
	12.6.4.8 category() [3/3]	123
	12.6.4.9 timestamp_string()	123
	12.6.4.10 timestamp() [1/3]	123
	12.6.4.11 timestamp() [2/3]	123
	12.6.4.12 timestamp() [3/3]	123
	12.6.4.13 time_as_pulses()	124
	12.6.4.14 time_as_measures()	124
	12.6.4.15 time_as_minutes()	124
	12.6.4.16 set_status_from_string()	124
	12.6.4.17 format_timestamp()	125
	12.6.4.18 stock_event_string()	125
	12.6.4.19 status_string()	125
	12.6.4.20 meta_string()	125
	12.6.4.21 seqspec_string()	125
	12.6.4.22 channel_string()	125
	12.6.4.23 data_string()	125
	12.6.4.24 analyze()	126
12.6.5	Field Documentation	126
	12.6.5.1 sm_category_names	126
	12.6.5.2 sm_channel_event_names	126
	12.6.5.3 sm_system_event_names	126
	12.6.5.4 sm_meta_event_names	127

CONTENTS xv

	12.6.5.5	sm_prop_event_names	 127
	12.6.5.6	sm_category_arrays	 127
	12.6.5.7	m_parent	 127
	12.6.5.8	m_category	 127
	12.6.5.9	m_name_category	 127
	12.6.5.10	m_format_timestamp	 127
	12.6.5.11	m_name_timestamp	 128
	12.6.5.12	m_name_status	 128
	12.6.5.13	m_name_meta	 128
	12.6.5.14	m_name_seqspec	 128
	12.6.5.15	m_name_channel	 128
	12.6.5.16	m_name_data	 128
12.7 seq64	::editable_e	vents Class Reference	 128
12.7.1	Member T	Typedef Documentation	 130
	12.7.1.1	Key	 130
	12.7.1.2	EventsPair	 130
	12.7.1.3	Events	 130
	12.7.1.4	iterator	 131
	12.7.1.5	const_iterator	 131
12.7.2	Constructe	or & Destructor Documentation	 131
	12.7.2.1	editable_events() [1/3]	 131
	12.7.2.2	editable_events() [2/3]	 131
	12.7.2.3	editable_events() [3/3]	 131
	12.7.2.4	~editable_events()	 131
12.7.3	Member F	Function Documentation	 132
	12.7.3.1	operator=()	 132
	12.7.3.2	timing()	 132
	12.7.3.3	string_to_pulses()	 132
	12.7.3.4	load_events()	 132
	12.7.3.5	save_events()	 132

xvi CONTENTS

12.7.3.7 begin() [1/2]		12.7.3.6 events()
12.7.3.9 end() [1/2]		12.7.3.7 begin() [1/2]
12.7.3.10 end() [2/2] 133 12.7.3.11 dref() [1/2] 133 12.7.3.12 dref() [2/2] 133 12.7.3.13 count() 133 12.7.3.14 add() [1/2] 134 12.7.3.15 add() [2/2] 134 12.7.3.16 replace() 134 12.7.3.16 replace() 134 12.7.3.18 clear() 134 12.7.3.19 current_event() [1/2] 135 12.7.3.20 current_event() [1/2] 135 12.7.4.1 eventslots 135 12.7.4.1 eventslots 135 12.7.5.1 m_events 135 12.7.5.2 m_current_event 135 12.7.5.3 m_sequence 135 12.7.5.4 m_midi_parameters 135 12.8.8 seq64::event Class Reference 136 12.8.1 Detailed Description 140 12.8.2.1 SysexContainer 140 12.8.3.1 event() [1/2] 140 12.8.3.2 event() [1/2] 140		12.7.3.8 begin() [2/2]
12.7.3.11 dref() [1/2] 133 12.7.3.12 dref() [2/2] 133 12.7.3.13 count() 133 12.7.3.14 add() [1/2] 134 12.7.3.15 add() [2/2] 134 12.7.3.16 replace() 134 12.7.3.17 remove() 134 12.7.3.18 clear() 134 12.7.3.19 current_event() [1/2] 135 12.7.3.20 current_event() [1/2] 135 12.7.4.7 Friends And Related Function Documentation 135 12.7.4.1 eventslots 135 12.7.5.1 m_events 135 12.7.5.2 m_current_event 135 12.7.5.3 m_sequence 135 12.7.5.4 m_midi_parameters 135 12.8 seq64::event Class Reference 136 12.8.1 Detailed Description 140 12.8.2 Member Typedel Documentation 140 12.8.3 Constructor & Destructor Documentation 140 12.8.3 Constructor & Destructor Documentation 140 12.8.3.1 event() [1/2] 140		12.7.3.9 end() [1/2]
12.7.3.12 dref() [2/2] 133 12.7.3.13 count() 133 12.7.3.14 add() [1/2] 134 12.7.3.15 add() [2/2] 134 12.7.3.16 replace() 134 12.7.3.16 replace() 134 12.7.3.17 remove() 134 12.7.3.19 current_event() [1/2] 135 12.7.3.20 current_event() [2/2] 135 12.7.4 Friends And Related Function Documentation 135 12.7.5.1 m_events 135 12.7.5 Field Documentation 135 12.7.5.2 m_current_event 135 12.7.5.3 m_sequence 135 12.7.5.4 m_midi_parameters 135 12.8.8 seq64:::event Class Reference 136 12.8.1 Detailed Description 140 12.8.2 Member Typedef Documentation 140 12.8.3 Constructor & Destructor Documentation 140 12.8.3.1 event() [1/2] 140 12.8.3.2 event() [1/2] 140		12.7.3.10 end() [2/2]
12.7.3.13 count() 133 12.7.3.14 add() [1/2] 134 12.7.3.15 add() [2/2] 134 12.7.3.16 replace() 134 12.7.3.17 remove() 134 12.7.3.18 clear() 134 12.7.3.19 current_event() [1/2] 135 12.7.3.20 current_event() [2/2] 135 12.7.4 Friends And Related Function Documentation 135 12.7.5 Field Documentation 135 12.7.5.1 m_events 135 12.7.5.2 m_current_event 135 12.7.5.3 m_sequence 135 12.7.5.4 m_midi_parameters 135 12.7.5.4 m_midi_parameters 135 12.8 seq64::event Class Reference 136 12.8.1 Detailed Description 140 12.8.2 Member Typedef Documentation 140 12.8.3.1 event() [1/2] 140 12.8.3.2 event() [1/2] 140		12.7.3.11 dref() [1/2]
12.7.3.14 add() [1/2] 134 12.7.3.15 add() [2/2] 134 12.7.3.16 replace() 134 12.7.3.17 remove() 134 12.7.3.18 clear() 134 12.7.3.19 current_event() [1/2] 135 12.7.3.20 current_event() [2/2] 135 12.7.4 Friends And Related Function Documentation 135 12.7.5 Field Documentation 135 12.7.5 Field Documentation 135 12.7.5.1 m_events 135 12.7.5.2 m_current_event 135 12.7.5.3 m_sequence 135 12.7.5.4 m_midi_parameters 135 12.8 seq64::event Class Reference 136 12.8.1 Detailed Description 140 12.8.2 Member Typedef Documentation 140 12.8.3 Constructor & Destructor Documentation 140 12.8.3.1 event() [1/2] 140 12.8.3.2 event() [2/2] 140		12.7.3.12 dref() [2/2]
12.7.3.15 add() [2/2] 134 12.7.3.16 replace() 134 12.7.3.17 remove() 134 12.7.3.18 clear() 134 12.7.3.19 current_event() [1/2] 135 12.7.3.20 current_event() [2/2] 135 12.7.4 Friends And Related Function Documentation 135 12.7.4.1 eventslots 135 12.7.5 Field Documentation 135 12.7.5.1 m_events 135 12.7.5.2 m_current_event 135 12.7.5.3 m_sequence 135 12.7.5.4 m_midi_parameters 135 12.8 seq64::event Class Reference 136 12.8.1 Detailed Description 140 12.8.2 Member Typedef Documentation 140 12.8.3 Constructor & Destructor Documentation 140 12.8.3.1 event() [1/2] 140 12.8.3.2 event() [2/2] 140		12.7.3.13 count()
12.7.3.16 replace() 134 12.7.3.17 remove() 134 12.7.3.18 clear() 134 12.7.3.19 current_event() [1/2] 135 12.7.3.20 current_event() [2/2] 135 12.7.4 Friends And Related Function Documentation 135 12.7.4.1 eventslots 135 12.7.5 Field Documentation 135 12.7.5.2 m_current_event 135 12.7.5.3 m_sequence 135 12.7.5.4 m_midi_parameters 135 12.8 seq64::event Class Reference 136 12.8.1 Detailed Description 140 12.8.2 Member Typedef Documentation 140 12.8.3.1 event() [1/2] 140 12.8.3.1 event() [1/2] 140		12.7.3.14 add() [1/2]
12.7.3.17 remove() 134 12.7.3.18 clear() 134 12.7.3.19 current_event() [1/2] 135 12.7.3.20 current_event() [2/2] 135 12.7.4 Friends And Related Function Documentation 135 12.7.4.1 eventslots 135 12.7.5 Field Documentation 135 12.7.5.1 m_events 135 12.7.5.2 m_current_event 135 12.7.5.3 m_sequence 135 12.7.5.4 m_midi_parameters 135 12.8 seq64::event Class Reference 136 12.8.1 Detailed Description 140 12.8.2 Member Typedef Documentation 140 12.8.3 Constructor & Destructor Documentation 140 12.8.3.1 event() [1/2] 140 12.8.3.2 event() [2/2] 140		12.7.3.15 add() [2/2]
12.7.3.18 clear() 134 12.7.3.19 current_event() [1/2] 135 12.7.3.20 current_event() [2/2] 135 12.7.4 Friends And Related Function Documentation 135 12.7.4.1 eventslots 135 12.7.5 Field Documentation 135 12.7.5.1 m_events 135 12.7.5.2 m_current_event 135 12.7.5.3 m_sequence 135 12.7.5.4 m_midi_parameters 135 12.8. seq64::event Class Reference 136 12.8.1 Detailed Description 140 12.8.2.1 SysexContainer 140 12.8.3.1 event() [1/2] 140 12.8.3.2 event() [2/2] 140		12.7.3.16 replace()
12.7.3.19 current_event() [1/2] 135 12.7.3.20 current_event() [2/2] 135 12.7.4 Friends And Related Function Documentation 135 12.7.4.1 eventslots 135 12.7.5 Field Documentation 135 12.7.5.1 m_events 135 12.7.5.2 m_current_event 135 12.7.5.3 m_sequence 135 12.7.5.4 m_midi_parameters 135 12.8 seq64::event Class Reference 136 12.8.1 Detailed Description 140 12.8.2 Member Typedef Documentation 140 12.8.3 Constructor & Destructor Documentation 140 12.8.3.1 event() [1/2] 140 12.8.3.2 event() [2/2] 140		12.7.3.17 remove()
12.7.3.20 current_event() [2/2] 135 12.7.4 Friends And Related Function Documentation 135 12.7.4.1 eventslots 135 12.7.5 Field Documentation 135 12.7.5.1 m_events 135 12.7.5.2 m_current_event 135 12.7.5.3 m_sequence 135 12.7.5.4 m_midi_parameters 135 12.8 seq64::event Class Reference 136 12.8.1 Detailed Description 140 12.8.2 Member Typedef Documentation 140 12.8.3 Constructor & Destructor Documentation 140 12.8.3.1 event() [1/2] 140 12.8.3.2 event() [2/2] 140		12.7.3.18 clear()
12.7.4 Friends And Related Function Documentation 135 12.7.4.1 eventslots 135 12.7.5 Field Documentation 135 12.7.5.1 m_events 135 12.7.5.2 m_current_event 135 12.7.5.3 m_sequence 135 12.7.5.4 m_midi_parameters 135 12.8 seq64::event Class Reference 136 12.8.1 Detailed Description 140 12.8.2 Member Typedef Documentation 140 12.8.3 Constructor & Destructor Documentation 140 12.8.3.1 event() [1/2] 140 12.8.3.2 event() [2/2] 140		12.7.3.19 current_event() [1/2]
12.7.4.1 eventslots 135 12.7.5 Field Documentation 135 12.7.5.1 m_events 135 12.7.5.2 m_current_event 135 12.7.5.3 m_sequence 135 12.7.5.4 m_midi_parameters 135 12.8 seq64::event Class Reference 136 12.8.1 Detailed Description 140 12.8.2 Member Typedef Documentation 140 12.8.3 Constructor & Destructor Documentation 140 12.8.3.1 event() [1/2] 140 12.8.3.2 event() [2/2] 140		12.7.3.20 current_event() [2/2]
12.7.5 Field Documentation 135 12.7.5.1 m_events 135 12.7.5.2 m_current_event 135 12.7.5.3 m_sequence 135 12.7.5.4 m_midi_parameters 135 12.8 seq64::event Class Reference 136 12.8.1 Detailed Description 140 12.8.2 Member Typedef Documentation 140 12.8.2.1 SysexContainer 140 12.8.3.1 event() [1/2] 140 12.8.3.2 event() [2/2] 140	12.7.4	Friends And Related Function Documentation
12.7.5.1 m_events 135 12.7.5.2 m_current_event 135 12.7.5.3 m_sequence 135 12.7.5.4 m_midi_parameters 135 12.8 seq64::event Class Reference 136 12.8.1 Detailed Description 140 12.8.2 Member Typedef Documentation 140 12.8.3 Constructor & Destructor Documentation 140 12.8.3.1 event() [1/2] 140 12.8.3.2 event() [2/2] 140		12.7.4.1 eventslots
12.7.5.2 m_current_event 135 12.7.5.3 m_sequence 135 12.7.5.4 m_midi_parameters 135 12.8 seq64::event Class Reference 136 12.8.1 Detailed Description 140 12.8.2 Member Typedef Documentation 140 12.8.2.1 SysexContainer 140 12.8.3 Constructor & Destructor Documentation 140 12.8.3.1 event() [1/2] 140 12.8.3.2 event() [2/2] 140	12.7.5	Field Documentation
12.7.5.3 m_sequence 135 12.7.5.4 m_midi_parameters 135 12.8 seq64::event Class Reference 136 12.8.1 Detailed Description 140 12.8.2 Member Typedef Documentation 140 12.8.2.1 SysexContainer 140 12.8.3 Constructor & Destructor Documentation 140 12.8.3.1 event() [1/2] 140 12.8.3.2 event() [2/2] 140		12.7.5.1 m_events
12.7.5.4 m_midi_parameters 135 12.8 seq64::event Class Reference 136 12.8.1 Detailed Description 140 12.8.2 Member Typedef Documentation 140 12.8.2.1 SysexContainer 140 12.8.3 Constructor & Destructor Documentation 140 12.8.3.1 event() [1/2] 140 12.8.3.2 event() [2/2] 140		12.7.5.2 m_current_event
12.8 seq64::event Class Reference 136 12.8.1 Detailed Description 140 12.8.2 Member Typedef Documentation 140 12.8.2.1 SysexContainer 140 12.8.3 Constructor & Destructor Documentation 140 12.8.3.1 event() [1/2] 140 12.8.3.2 event() [2/2] 140		12.7.5.3 m_sequence
12.8.1 Detailed Description 140 12.8.2 Member Typedef Documentation 140 12.8.2.1 SysexContainer 140 12.8.3 Constructor & Destructor Documentation 140 12.8.3.1 event() [1/2] 140 12.8.3.2 event() [2/2] 140		12.7.5.4 m_midi_parameters
12.8.2 Member Typedef Documentation 140 12.8.2.1 SysexContainer 140 12.8.3 Constructor & Destructor Documentation 140 12.8.3.1 event() [1/2] 140 12.8.3.2 event() [2/2] 140	12.8 seq64:	event Class Reference
12.8.2.1 SysexContainer 140 12.8.3 Constructor & Destructor Documentation 140 12.8.3.1 event() [1/2] 140 12.8.3.2 event() [2/2] 140	12.8.1	Detailed Description
12.8.3 Constructor & Destructor Documentation	12.8.2	Member Typedef Documentation
12.8.3.1 event() [1/2]		12.8.2.1 SysexContainer
12.8.3.2 event() [2/2]	12.8.3	Constructor & Destructor Documentation
		12.8.3.1 event() [1/2]
12.8.3.3 ~event()		12.8.3.2 event() [2/2]
		12.8.3.3 ~event()

CONTENTS xvii

2.8.4	Member Function Documentation	41
	12.8.4.1 operator=()	41
	12.8.4.2 operator<()	41
	12.8.4.3 set_timestamp()	42
	12.8.4.4 get_timestamp()	42
	12.8.4.5 get_channel()	42
	12.8.4.6 check_channel()	42
	12.8.4.7 is_channel_msg()	43
	12.8.4.8 is_one_byte_msg()	43
	12.8.4.9 is_two_byte_msg()	43
	12.8.4.10 is_note_msg()	44
	12.8.4.11 is_strict_note_msg()	44
	12.8.4.12 is_desired_cc_or_not_cc()	44
	12.8.4.13 mod_timestamp()	45
	12.8.4.14 set_status() [1/2]	45
	12.8.4.15 set_status() [2/2]	46
	12.8.4.16 set_status_keep_channel()	46
	12.8.4.17 set_channel()	46
	12.8.4.18 get_status()	47
	12.8.4.19 set_data() [1/2]	47
	12.8.4.20 set_data() [2/2]	47
	12.8.4.21 get_data()	47
	12.8.4.22 increment_data1()	47
	12.8.4.23 decrement_data1()	48
	12.8.4.24 increment_data2()	48
	12.8.4.25 decrement_data2()	48
	12.8.4.26 append_sysex() [1/2]	48
	12.8.4.27 append_sysex() [2/2]	48
	12.8.4.28 restart_sysex()	48
	12.8.4.29 get_sysex() [1/2]	49

xviii CONTENTS

	12.8.4.30 get_sysex() [2/2]	149
	12.8.4.31 set_sysex_size()	149
	12.8.4.32 get_sysex_size()	149
	12.8.4.33 link()	149
	12.8.4.34 get_linked()	149
	12.8.4.35 is_linked()	149
	12.8.4.36 clear_link()	149
	12.8.4.37 paint()	149
	12.8.4.38 unpaint()	150
	12.8.4.39 is_painted()	150
	12.8.4.40 mark()	150
	12.8.4.41 unmark()	150
	12.8.4.42 is_marked()	150
	12.8.4.43 select()	150
	12.8.4.44 unselect()	150
	12.8.4.45 is_selected()	150
	12.8.4.46 make_clock()	150
	12.8.4.47 data()	150
	12.8.4.48 get_note()	150
	12.8.4.49 set_note()	150
	12.8.4.50 transpose_note()	151
	12.8.4.51 get_note_velocity()	151
	12.8.4.52 set_note_velocity()	151
	12.8.4.53 is_note_on()	151
	12.8.4.54 is_note_off()	151
	12.8.4.55 is_note()	152
	12.8.4.56 is_note_off_recorded()	152
	12.8.4.57 print()	152
	12.8.4.58 get_rank()	152
12.8.5	Field Documentation	152

CONTENTS xix

	12.8.5.1 m_timestamp
	12.8.5.2 m_status
	12.8.5.3 m_channel
	12.8.5.4 m_data
	12.8.5.5 m_sysex
	12.8.5.6 m_sysex_size
	12.8.5.7 m_linked
	12.8.5.8 m_has_link
	12.8.5.9 m_selected
	12.8.5.10 m_marked
	12.8.5.11 m_painted
12.9 seq64	:event_list::event_key Class Reference
12.9.1	Detailed Description
12.9.2	Constructor & Destructor Documentation
	12.9.2.1 event_key() [1/2]
	12.9.2.2 event_key() [2/2]
12.9.3	Member Function Documentation
	12.9.3.1 operator<()
12.9.4	Field Documentation
	12.9.4.1 m_timestamp
	12.9.4.2 m_rank
12.10seq64	:event_list Class Reference
12.10.	Detailed Description
12.10.	2 Member Typedef Documentation
	12.10.2.1 Events
	12.10.2.2 EventsPair
	12.10.2.3 iterator
	12.10.2.4 const_iterator
12.10.	3 Constructor & Destructor Documentation
	12.10.3.1 event_list() [1/2]

12	2.10.3.2 event_list() [2/2]	158
12	2.10.3.3 ~event_list()	158
12.10.4 M	ember Function Documentation	159
12	2.10.4.1 operator=()	159
12	2.10.4.2 begin() [1/2]	159
12	2.10.4.3 begin() [2/2]	159
12	2.10.4.4 end() [1/2]	159
12		159
12	2.10.4.6 count()	159
12	2.10.4.7 empty()	159
12	2.10.4.8 add()	160
12	2.10.4.9 is_modified()	160
12	2.10.4.10unmodify()	160
12	2.10.4.11remove()	160
12	2.10.4.12clear()	161
12	2.10.4.13merge()	161
12	.10.4.14dref() [1/2]	161
12	.10.4.15dref() [2/2]	162
12	2.10.4.1dink_new()	162
12	2.10.4.17clear_links()	162
12	2.10.4.18verify_and_link()	162
12	2.10.4.19mark_selected()	162
12	.10.4.20mark_out_of_range()	163
12	.10.4.21mark_all()	163
12	.10.4.22unmark_all()	163
12	2.10.4.23remove_marked()	163
12		163
12	2.10.4.25count_selected_notes()	163
12	2.10.4.26any_selected_notes()	164
12	2.10.4.27count_selected_events()	164

CONTENTS xxi

12.10.4.28select_all()	164
12.10.4.29unselect_all()	164
12.10.4.3@rint()	164
12.10.4.31events()	164
12.10.5 Friends And Related Function Documentation	165
12.10.5.1 editable_events	165
12.10.5.2 midi_container	165
12.10.5.3 midi_splitter	165
12.10.5.4 sequence	165
12.10.6 Field Documentation	165
12.10.6.1 m_events	165
12.10.6.2 m_is_modified	165
12.11seq64::eventedit Class Reference	166
12.11.1 Constructor & Destructor Documentation	169
12.11.1.1 eventedit()	169
12.11.1.2 ~eventedit()	170
12.11.2 Member Function Documentation	171
12.11.2.1 enqueue_draw()	171
12.11.2.2 set_seq_title()	171
12.11.2.3 set_seq_time_sig()	171
12.11.2.4 set_seq_ppqn()	171
12.11.2.5 set_seq_count()	171
12.11.2.6 set_event_category()	171
12.11.2.7 set_event_timestamp()	172
12.11.2.8 set_event_name()	172
12.11.2.9 set_event_data_0()	172
12.11.2.10set_event_data_1()	172
12.11.2.11perf_modify()	172
12.11.2.12set_dirty()	173
12.11.2.13v_adjustment() [1/2]	173

xxii CONTENTS

12.11.2.14v_adjustment() [2/2]
12.11.2.15change_focus()
12.11.2.16close_out()
12.11.2.17handle_close()
12.11.2.18handle_delete()
12.11.2.19handle_insert()
12.11.2.20handle_modify()
12.11.2.21handle_save()
12.11.2.22handle_cancel()
12.11.2.23on_realize()
12.11.2.24on_set_focus()
12.11.2.25on_focus_in_event()
12.11.2.26on_focus_out_event()
12.11.2.27on_key_press_event()
12.11.2.28on_delete_event()
12.11.3 Friends And Related Function Documentation
12.11.3.1 eventslots
12.11.4 Field Documentation
12.11.4.1 m_table
12.11.4.2 m_vadjust
12.11.4.3 m_vscroll
12.11.4.4 m_eventslots
12.11.4.5 m_htopbox
12.11.4.6 m_showbox
12.11.4.7 m_editbox
12.11.4.8 m_optsbox
12.11.4.9 m_bottbox
12.11.4.10m_rightbox
12.11.4.11m_button_del
12.11.4.12m_button_ins

CONTENTS xxiii

12.11.4.13m_button_modify	77
12.11.4.14m_button_save	77
12.11.4.15m_button_cancel	78
12.11.4.16m_label_seq_name	78
12.11.4.17m_label_time_sig	78
12.11.4.18m_label_ppqn	78
12.11.4.19m_label_channel	78
12.11.4.20m_label_ev_count	78
12.11.4.21m_label_spacer	78
12.11.4.22m_label_modified	78
12.11.4.23m_label_category	78
12.11.4.24m_entry_ev_timestamp	79
12.11.4.25m_entry_ev_name	79
12.11.4.26m_entry_ev_data_0	79
12.11.4.27m_entry_ev_data_1	79
12.11.4.28m_label_time_fmt	79
12.11.4.29m_label_right	79
12.11.4.30m_seq	79
12.11.4.31m_have_focus	79
12.12seq64::eventslots Class Reference	80
12.12.1 Constructor & Destructor Documentation	84
12.12.1.1 eventslots()	84
12.12.1.2 ~eventslots()	84
12.12.2 Member Function Documentation	84
12.12.2.1 event_count()	84
12.12.2.2 line_count()	84
12.12.2.3 line_maximum()	84
12.12.2.4 line_increment()	84
12.12.2.5 top_index()	84
12.12.2.6 current_index()	84

xxiv CONTENTS

12.12.2.7 pager_index()
12.12.2.8 load_events()
12.12.2.9 set_current_event()
12.12.2.1@nsert_event() [1/2]
12.12.2.11insert_event() [2/2]
12.12.2.12delete_current_event()
12.12.2.13modify_current_event()
12.12.2.14save_events()
12.12.2.15select_event()
12.12.2.16set_text()
12.12.2.17enqueue_draw()
12.12.2.1&onvert_y()
12.12.2.19draw_event()
12.12.2.20draw_events()
12.12.2.21change_vert()
12.12.2.22page_movement()
12.12.2.23page_topper()
12.12.2.24decrement_top()
12.12.2.25ncrement_top()
12.12.2.26decrement_current()
12.12.2.27increment_current()
12.12.2.2&decrement_bottom()
12.12.2.29ncrement_bottom()
12.12.2.30on_realize()
12.12.2.31on_expose_event()
12.12.2.32on_button_press_event()
12.12.2.33on_button_release_event()
12.12.2.34on_focus_in_event()
12.12.2.35on_focus_out_event()
12.12.2.36on_scroll_event()

CONTENTS xxv

12.12.2.37on_size_allocate())4
12.12.2.38on_move_up()) 4
12.12.2.39on_move_down())4
12.12.2.40on_frame_up()) 4
12.12.2.41on_frame_down()) 5
12.12.2.42on_frame_home()) 5
12.12.2.43on_frame_end()) 5
12.12.3 Friends And Related Function Documentation) 5
12.12.3.1 eventedit) 5
12.12.4 Field Documentation) 5
12.12.4.1 m_parent) 5
12.12.4.2 m_seq) 5
12.12.4.3 m_event_container)5
12.12.4.4 m_slots_chars) 5
12.12.4.5 m_char_w)5
12.12.4.6 m_setbox_w	96
12.12.4.7 m_slots_x)6
12.12.4.8 m_slots_y)6
12.12.4.9 m_event_count	96
12.12.4.10m_line_count	96
12.12.4.11m_line_maximum)6
12.12.4.12m_line_overlap)6
12.12.4.13m_top_index)6
12.12.4.14m_current_index	<u>)</u> 6
12.12.4.15m_top_iterator) 7
12.12.4.16m_bottom_iterator) 7
12.12.4.17m_current_iterator	3 7
12.12.4.18m_pager_index19) 7
12.13seq64::font Class Reference) 7
12.13.1 Member Enumeration Documentation	98

xxvi CONTENTS

	12.13.1.1 Color	198
12.13.	2 Constructor & Destructor Documentation	199
	12.13.2.1 font()	199
12.13.	3 Member Function Documentation	199
	12.13.3.1 init()	199
	12.13.3.2 render_string_on_drawable()	199
	12.13.3.3 char_width()	200
	12.13.3.4 char_height()	200
	12.13.3.5 padded_height()	200
12.13.	4 Field Documentation	200
	12.13.4.1 m_use_new_font	200
	12.13.4.2 m_cell_w	200
	12.13.4.3 m_cell_h	200
	12.13.4.4 m_font_w	200
	12.13.4.5 m_font_h	200
	12.13.4.6 m_offset	200
	12.13.4.7 m_padded_h	201
	12.13.4.8 m_pixmap	201
	12.13.4.9 m_black_pixmap	201
	12.13.4.10m_white_pixmap	201
	12.13.4.11m_b_on_y_pixmap	201
	12.13.4.12m_y_on_b_pixmap	201
	12.13.4.13m_b_on_c_pixmap	201
	12.13.4.14m_c_on_b_pixmap	202
	12.13.4.15m_clip_mask	202
12.14seq64	::FruityPerfInput Class Reference	202
12.14.	1 Constructor & Destructor Documentation	203
	12.14.1.1 FruityPerfInput()	203
12.14.	2 Member Function Documentation	203
	12.14.2.1 on_button_press_event()	203

CONTENTS xxvii

12.14.2.2 on_button_release_event()	204
12.14.2.3 on_motion_notify_event()	204
12.14.2.4 update_mouse_pointer()	205
12.14.2.5 on_left_button_pressed()	205
12.14.2.6 on_right_button_pressed()	205
12.14.2.7 activate_adding()	206
12.14.2.8 handle_motion_key()	206
12.14.3 Friends And Related Function Documentation	206
12.14.3.1 perfroll	206
12.14.4 Field Documentation	206
12.14.4.1 m_current_x	206
12.14.4.2 m_current_y	206
12.15seq64::FruitySeqEventInput Struct Reference	206
12.15.1 Constructor & Destructor Documentation	207
12.15.1.1 FruitySeqEventInput()	207
12.15.2 Member Function Documentation	207
12.15.2.1 update_mouse_pointer()	207
12.15.2.2 on_button_press_event()	207
12.15.2.3 on_button_release_event()	208
12.15.2.4 on_motion_notify_event()	209
12.15.3 Field Documentation	209
12.15.3.1 m_justselected_one	209
12.15.3.2 m_is_drag_pasting_start	209
12.15.3.3 m_is_drag_pasting	209
12.16seq64::FruitySeqRollInput Class Reference	209
12.16.1 Constructor & Destructor Documentation	210
12.16.1.1 FruitySeqRollInput()	210
12.16.2 Member Function Documentation	210
12.16.2.1 update_mouse_pointer()	210
12.16.2.2 on_button_press_event()	210

xxviii CONTENTS

12.16.2.3 on_button_release_event()
12.16.2.4 on_motion_notify_event()
12.16.3 Field Documentation
12.16.3.1 m_erase_painting
12.16.3.2 m_drag_paste_start_pos
12.17seq64::gui_assistant Class Reference
12.17.1 Detailed Description
12.17.2 Constructor & Destructor Documentation
12.17.2.1 gui_assistant()
12.17.2.2 ~gui_assistant()
12.17.3 Member Function Documentation
12.17.3.1 quit()
12.17.3.2 jack_idle_connect()
12.17.3.3 lash_timeout_connect()
12.17.3.4 keys() [1/2]
12.17.3.5 keys() [2/2]
12.17.4 Field Documentation
12.17.4.1 m_keys_perform
12.18seq64::gui_assistant_gtk2 Class Reference
12.18.1 Constructor & Destructor Documentation
12.18.1.1 gui_assistant_gtk2()
12.18.1.2 ~gui_assistant_gtk2()
12.18.2 Member Function Documentation
12.18.2.1 quit()
12.18.2.2 lash_timeout_connect()
12.18.2.3 jack_idle_connect()
12.18.3 Field Documentation
12.18.3.1 sm_internal_keys
12.19seq64::gui_drawingarea_gtk2 Class Reference
12.19.1 Detailed Description

CONTENTS xxix

12.19.2 Constructor & Destructor Documentation
12.19.2.1 gui_drawingarea_gtk2() [1/3]
12.19.2.2 gui_drawingarea_gtk2() [2/3]
12.19.2.3 gui_drawingarea_gtk2() [3/3]
12.19.2.4 ~gui_drawingarea_gtk2()
12.19.3 Member Function Documentation
12.19.3.1 operator=()
12.19.3.2 window_x()
12.19.3.3 window_y()
12.19.3.4 current_x()
12.19.3.5 current_y()
12.19.3.6 drop_x()
12.19.3.7 drop_y()
12.19.3.8 force_draw()
12.19.3.9 perf()
12.19.3.10clear_window()
12.19.3.11set_line()
12.19.3.12draw_line() [1/6]
12.19.3.13draw_line() [2/6]
12.19.3.14draw_line_on_pixmap() [1/2]
12.19.3.15draw_line_on_pixmap() [2/2]
12.19.3.16draw_line() [3/6]
12.19.3.17draw_line() [4/6]
12.19.3.18draw_line() [5/6]
12.19.3.19draw_line() [6/6]
12.19.3.20render_string()
12.19.3.21render_string_on_pixmap()
12.19.3.22draw_rectangle() [1/6]
12.19.3.23draw_rectangle() [2/6]
12.19.3.24draw_rectangle() [3/6]

1	2.19.3.25draw_rectangle() [4/6]	227
1	2.19.3.26draw_rectangle() [5/6]	228
1	2.19.3.27draw_rectangle() [6/6]	228
1	2.19.3.28draw_rectangle_on_pixmap() [1/2]	229
1	2.19.3.29draw_rectangle_on_pixmap() [2/2]	229
1	2.19.3.30draw_normal_rectangle_on_pixmap()	230
1	2.19.3.31draw_drawable()	230
1	2.19.3.32scroll_hadjust()	230
1	2.19.3.33scroll_vadjust()	230
1	2.19.3.34scroll_hset()	231
1	2.19.3.35scroll_vset()	231
1	2.19.3.36set_current_drop_x()	231
1	2.19.3.37set_current_drop_y()	231
1	2.19.3.38gtk_drawarea_init()	231
1	2.19.3.39on_realize()	232
12.19.4 F	eld Documentation	232
1	2.19.4.1 m_gc	232
1	2.19.4.2 m_window	232
1	2.19.4.3 m_vadjust	232
1	2.19.4.4 m_hadjust	232
1	2.19.4.5 m_pixmap	232
1	2.19.4.6 m_background	232
1	2.19.4.7 m_foreground	232
1	2.19.4.8 m_mainperf	233
1	2.19.4.9 m_window_x	233
1	2.19.4.10m_window_y	233
1	2.19.4.11m_current_x	233
1	2.19.4.12m_current_y	233
1	2.19.4.13m_drop_x	233
1	2.19.4.14m_drop_y	233

CONTENTS xxxi

12.20seq64::gui_palette_gtk2 Class Reference
12.20.1 Detailed Description
12.20.2 Member Typedef Documentation
12.20.2.1 Color
12.20.3 Constructor & Destructor Documentation
12.20.3.1 gui_palette_gtk2()
12.20.3.2 ~gui_palette_gtk2()
12.20.4 Member Function Documentation
12.20.4.1 load_inverse_palette()
12.20.4.2 is_inverse()
12.20.4.3 line_color()
12.20.4.4 progress_color()
12.20.4.5 black()
12.20.4.6 dark_red()
12.20.4.7 dark_green()
12.20.4.8 dark_orange()
12.20.4.9 dark_blue()
12.20.4.1@dark_magenta()
12.20.4.11dark_cyan()
12.20.4.12white()
12.20.4.13grey()
12.20.4.14dark_grey()
12.20.4.15ight_grey()
12.20.4.16red()
12.20.4.17orange()
12.20.4.18yellow()
12.20.4.19green()
12.20.4.20blue()
12.20.4.21black_paint()
12.20.4.22white_paint()

xxxii CONTENTS

1:	2.20.4.23black_key()	240
1	12.20.4.24white_key()	240
1:	12.20.4.25bg_color() [1/2]	24 ⁻
1:	12.20.4.26bg_color() [2/2]	24
1:	2.20.4.27fg_color() [1/2]	24
1:	2.20.4.2&g_color() [2/2]	24
12.20.5 F	Field Documentation	24
1:	2.20.5.1 m_is_inverse	24
1:	2.20.5.2 m_black	24
1:	2.20.5.3 m_dk_red	24
1:	2.20.5.4 m_dk_green	24
1:	2.20.5.5 m_dk_orange	24
1:	2.20.5.6 m_dk_blue	242
13	2.20.5.7 m_dk_magenta	242
13	2.20.5.8 m_dk_cyan	242
13	2.20.5.9 m_red	242
13	2.20.5.10m_white	242
1:	2.20.5.11m_orange	242
13	2.20.5.12m_yellow	242
13	2.20.5.13m_green	242
13	2.20.5.14m_blue	242
13	2.20.5.15m_grey	242
1:	2.20.5.16m_dk_grey	243
13	2.20.5.17m_lt_grey	243
13	2.20.5.18m_blk_paint	243
13	2.20.5.19m_wht_paint	240
13	2.20.5.20m_blk_key	243
1:	2.20.5.21m_wht_key	240
1:	2.20.5.22m_line_color	240
1:	2.20.5.23m_progress_color	243

CONTENTS xxxiii

12.20.5.24m_bg_color	43
12.20.5.25m_fg_color	43
12.21seq64::gui_window_gtk2 Class Reference	44
12.21.1 Constructor & Destructor Documentation	45
12.21.1.1 gui_window_gtk2()	45
12.21.1.2 ~gui_window_gtk2()	46
12.21.2 Member Function Documentation	46
12.21.2.1 perf()	46
12.21.2.2 quit()	46
12.21.2.3 redraw_period_ms()	46
12.21.2.4 is_realized()	46
12.21.2.5 scroll_hadjust()	46
12.21.2.6 scroll_vadjust()	46
12.21.2.7 scroll_hset()	47
12.21.2.8 scroll_vset()	47
12.21.2.9 on_realize()	47
12.21.3 Field Documentation	47
12.21.3.1 m_mainperf	47
12.21.3.2 m_window_x	47
12.21.3.3 m_window_y	48
12.21.3.4 m_redraw_period_ms	48
12.21.3.5 m_is_realized	48
12.22seq64::jack_assistant Class Reference	48
12.22.1 Constructor & Destructor Documentation	52
12.22.1.1 jack_assistant()	52
12.22.1.2 ~jack_assistant()	52
12.22.2 Member Function Documentation	52
12.22.2.1 parent() [1/2]	52
12.22.2.2 parent() [2/2]	52
12.22.2.3 is_running()	52

12.22.2.4 is_master()
12.22.2.5 get_ppqn()
12.22.2.6 get_beat_width()
12.22.2.7 set_beat_width()
12.22.2.8 get_beats_per_measure()
12.22.2.9 set_beats_per_measure()
12.22.2.10get_beats_per_minute()
12.22.2.11set_beats_per_minute()
12.22.2.12\text{transport_state()}
12.22.2.13\text{transport_not_starting()}
12.22.2.14nit()
12.22.2.15deinit()
12.22.2.16session_event()
12.22.2.17start()
12.22.2.18stop()
12.22.2.19position()
12.22.2.2@utput()
12.22.2.21set_ppqn()
12.22.2.22get_jack_tick()
12.22.2.23get_jack_pos()
12.22.2.24toggle_jack_mode()
12.22.2.25set_jack_mode()
12.22.2.26get_jack_mode()
12.22.2.27get_jack_stop_tick()
12.22.2.28set_jack_stop_tick()
12.22.2.29ack_frame_rate()
12.22.2.30get_follow_transport()
12.22.2.31set_follow_transport()
12.22.2.32oggle_follow_transport()
12.22.2.33toggle_song_start_mode()

CONTENTS XXXV

	12.22.2.34song_start_mode()	259
	12.22.2.35set_start_from_perfedit()	259
	12.22.2.3&lient()	259
	12.22.2.37client_name()	259
	12.22.2.3&lient_uuid()	259
	12.22.2.39set_jack_running()	259
	12.22.2.4@ick_multiplier()	259
	12.22.2.41info_message()	259
	12.22.2.42error_message()	260
	12.22.2.43client_open()	260
	12.22.2.44get_jack_client_info()	261
	12.22.2.45show_statuses()	261
	12.22.2.46show_position()	261
	12.22.2.47sync()	262
	12.22.2.4&set_position()	263
12.22.3	3 Friends And Related Function Documentation	263
	12.22.3.1 jack_process_callback	263
	12.22.3.2 jack_shutdown_callback	264
	12.22.3.3 jack_sync_callback	264
	12.22.3.4 jack_timebase_callback	264
	12.22.3.5 jack_session_callback	266
12.22.4	4 Field Documentation	266
	12.22.4.1 sm_status_pairs	266
	12.22.4.2 m_jack_parent	266
	12.22.4.3 m_jack_client	266
	12.22.4.4 m_jack_client_name	266
	12.22.4.5 m_jack_client_uuid	266
	12.22.4.6 m_jack_frame_current	267
	12.22.4.7 m_jack_frame_last	267
	12.22.4.8 m_jack_pos	267

xxxvi CONTENTS

12.22.4.9 m_jack_transport_state	. 267
12.22.4.10m_jack_transport_state_last	. 267
12.22.4.11m_jack_tick	. 267
12.22.4.12m_jsession_ev	. 267
12.22.4.13m_jack_running	. 267
12.22.4.14m_jack_master	. 267
12.22.4.15m_jack_frame_rate	. 268
12.22.4.16m_toggle_jack	. 268
12.22.4.17m_jack_stop_tick	. 268
12.22.4.18m_follow_transport	. 268
12.22.4.19m_ppqn	. 268
12.22.4.20m_beats_per_measure	. 268
12.22.4.21m_beat_width	. 268
12.22.4.22m_beats_per_minute	. 268
12.23seq64::jack_scratchpad Class Reference	. 268
12.23.1 Detailed Description	. 269
12.23.2 Field Documentation	. 269
12.23.2.1 js_current_tick	. 269
12.23.2.2 js_total_tick	. 269
12.23.2.3 js_clock_tick	. 269
12.23.2.4 js_jack_stopped	. 270
12.23.2.5 js_dumping	. 270
12.23.2.6 js_init_clock	. 270
12.23.2.7 js_looping	. 270
12.23.2.8 js_playback_mode	. 270
12.23.2.9 js_ticks_converted	. 270
12.23.2.1 gs_ticks_delta	. 270
12.23.2.11js_ticks_converted_last	. 270
12.23.2.14s_delta_tick_frac	. 270
12.24seq64::jack_status_pair_t Struct Reference	. 270

CONTENTS xxxvii

12.24.1 Field Documentation	271
12.24.1.1 jf_bit	
12.24.1.2 jf_meaning	
12.25seq64::keybindentry Class Reference	
12.25.1 Member Enumeration Documentation	272
12.25.1.1 type	272
12.25.2 Constructor & Destructor Documentation	272
12.25.2.1 keybindentry()	272
12.25.3 Member Function Documentation	273
12.25.3.1 set()	273
12.25.3.2 on_key_press_event()	273
12.25.4 Friends And Related Function Documentation	273
12.25.4.1 options	273
12.25.5 Field Documentation	273
12.25.5.1 m_key	273
12.25.5.2 m_type	273
12.25.5.3 m_perf	273
12.25.5.4 m_slot	274
12.26seq64::keys_perform Class Reference	274
12.26.1 Detailed Description	281
12.26.2 Member Typedef Documentation	281
12.26.2.1 SlotMap	281
12.26.2.2 RevSlotMap	281
12.26.3 Constructor & Destructor Documentation	281
12.26.3.1 keys_perform()	281
12.26.3.2 ~keys_perform()	282
12.26.4 Member Function Documentation	282
12.26.4.1 set_keys()	282
12.26.4.2 get_keys()	282
12.26.4.3 bpm_up() [1/2]	
$\cdot = \cdot \circ \cdot \circ$	_

xxxviii CONTENTS

12.26.4.4 bpm_up() [2/2]
12.26.4.5 bpm_dn() [1/2]
12.26.4.6 bpm_dn() [2/2]
12.26.4.7 replace() [1/2]
12.26.4.8 replace() [2/2]
12.26.4.9 queue() [1/2]
12.26.4.10queue() [2/2]
12.26.4.11keep_queue() [1/2]
12.26.4.12keep_queue() [2/2]
12.26.4.13snapshot_1() [1/2]
12.26.4.14snapshot_1() [2/2]
12.26.4.15snapshot_2() [1/2]
12.26.4.16snapshot_2() [2/2]
12.26.4.17screenset_up() [1/2]
12.26.4.18screenset_up() [2/2]
12.26.4.1%creenset_dn() [1/2]
12.26.4.20screenset_dn() [2/2]
12.26.4.21set_playing_screenset() [1/2]
12.26.4.23et_playing_screenset() [2/2]
12.26.4.23group_on() [1/2]
12.26.4.24group_on() [2/2]
12.26.4.25group_off() [1/2]
12.26.4.26group_off() [2/2]
12.26.4.27group_learn() [1/2]
12.26.4.28group_learn() [2/2]
12.26.4.29start() [1/2]
12.26.4.30start() [2/2]
12.26.4.31pause() [1/2]
12.26.4.32pause() [2/2]
12.26.4.33pattern_edit() [1/2]

CONTENTS xxxix

12.26.4.34pattern_edit() [2/2]
12.26.4.35event_edit() [1/2]
12.26.4.36event_edit() [2/2]
12.26.4.37stop() [1/2]
12.26.4.38stop() [2/2]
12.26.4.39song_mode() [1/2]
12.26.4.40song_mode() [2/2] 288
12.26.4.41menu_mode() [1/2]
12.26.4.42menu_mode() [2/2]
12.26.4.43follow_transport() [1/2]
12.26.4.44follow_transport() [2/2]
12.26.4.45fast_forward() [1/2] 288
12.26.4.46fast_forward() [2/2]
12.26.4.47rewind() [1/2]
12.26.4.48rewind() [2/2]
12.26.4.49pointer_position() [1/2]
12.26.4.50pointer_position() [2/2]
12.26.4.51toggle_mutes() [1/2] 289
12.26.4.52oggle_mutes() [2/2] 289
12.26.4.53toggle_jack() [1/2] 289
12.26.4.54toggle_jack() [2/2] 289
12.26.4.55tap_bpm() [1/2]
12.26.4.5@ap_bpm() [2/2]
12.26.4.57show_ui_sequence_key() [1/2]
12.26.4.58show_ui_sequence_key() [2/2]
12.26.4.59show_ui_sequence_number() [1/2]
12.26.4.60show_ui_sequence_number() [2/2]
12.26.4.61get_key_events()
12.26.4.62get_key_groups()
12.26.4.63get_key_events_rev()

xI CONTENTS

12.26.4.64get_key_groups_rev()
12.26.4.65ookup_keyevent_key()
12.26.4.6dookup_keyevent_seq()
12.26.4.67lookup_keygroup_key()
12.26.4.68ookup_keygroup_group()
12.26.4.69key_name()
12.26.4.70set_all_key_events()
12.26.4.71set_all_key_groups()
12.26.4.72set_key_event()
12.26.4.73set_key_group()
12.26.4.74at_bpm_up()
12.26.4.75at_bpm_dn()
12.26.4.76at_replace()
12.26.4.77at_queue()
12.26.4.78at_keep_queue()
12.26.4.79at_snapshot_1()
12.26.4.80at_snapshot_2()
12.26.4.81at_screenset_up()
12.26.4.82at_screenset_dn()
12.26.4.83at_set_playing_screenset()
12.26.4.84at_group_on()
12.26.4.85at_group_off()
12.26.4.86at_group_learn()
12.26.4.87at_start()
12.26.4.88at_pause()
12.26.4.89at_song_mode()
12.26.4.90at_toggle_jack()
12.26.4.91at_menu_mode()
12.26.4.92at_follow_transport()
12.26.4.93at_fast_forward()

CONTENTS xli

12.26.4.94at_rewind()	296
12.26.4.95at_pointer_position()	296
12.26.4.96at_toggle_mutes()	296
12.26.4.97at_tap_bpm()	296
12.26.4.98at_pattern_edit()	296
12.26.4.99at_event_edit()	296
12.26.4.10@t_stop()	296
12.26.4.10at_show_ui_sequence_key()	296
12.26.4.102t_show_ui_sequence_number()	297
12.26.5 Friends And Related Function Documentation	297
12.26.5.1 options	297
12.26.5.2 perform	297
12.26.5.3 optionsfile	297
12.26.6 Field Documentation	297
12.26.6.1 m_key_show_ui_sequence_key	297
12.26.6.2 m_key_show_ui_sequence_number	297
12.26.6.3 m_key_events	297
12.26.6.4 m_key_groups	297
12.26.6.5 m_key_events_rev	298
12.26.6.6 m_key_groups_rev	298
12.26.6.7 m_key_bpm_up	298
12.26.6.8 m_key_bpm_dn	298
12.26.6.9 m_key_replace	298
12.26.6.10m_key_queue	298
12.26.6.11m_key_keep_queue	298
12.26.6.12m_key_snapshot_1	298
12.26.6.13m_key_snapshot_2	298
12.26.6.14m_key_screenset_up	299
12.26.6.15m_key_screenset_dn	299
12.26.6.16m_key_set_playing_screenset	299

xlii CONTENTS

12.26.6.17m_key_group_on	299
12.26.6.18m_key_group_off	299
12.26.6.19m_key_group_learn	299
12.26.6.20m_key_start	299
12.26.6.21m_key_pause	299
12.26.6.22m_key_song_mode	299
12.26.6.23m_key_toggle_jack	299
12.26.6.24m_key_menu_mode	300
12.26.6.25m_key_follow_transport	300
12.26.6.26m_key_rewind	300
12.26.6.27m_key_fast_forward	300
12.26.6.28m_key_pointer_position	300
12.26.6.29m_key_toggle_mutes	300
12.26.6.30m_key_tap_bpm	300
12.26.6.31m_key_pattern_edit	300
12.26.6.32m_key_event_edit	300
12.26.6.33m_key_stop	300
12.27seq64::keys_perform_gtk2 Class Reference	301
12.27.1 Detailed Description	302
12.27.2 Constructor & Destructor Documentation	302
12.27.2.1 keys_perform_gtk2()	302
12.27.2.2 ~keys_perform_gtk2()	302
12.27.3 Member Function Documentation	302
12.27.3.1 key_name()	302
12.27.3.2 set_all_key_events()	302
12.27.3.3 set_all_key_groups()	303
12.28seq64::keys_perform_transfer Struct Reference	303
12.28.1 Field Documentation	303
12.28.1.1 kpt_bpm_up	303
12.28.1.2 kpt_bpm_dn	304

CONTENTS xliii

12.28.1.3 kpt_screenset_up	 304
12.28.1.4 kpt_screenset_dn	 304
12.28.1.5 kpt_set_playing_screenset	 304
12.28.1.6 kpt_group_on	 304
12.28.1.7 kpt_group_off	 304
12.28.1.8 kpt_group_learn	 304
12.28.1.9 kpt_replace	 304
12.28.1.10kpt_queue	 304
12.28.1.11kpt_keep_queue	 304
12.28.1.12kpt_snapshot_1	 305
12.28.1.13kpt_snapshot_2	 305
12.28.1.14kpt_start	 305
12.28.1.15kpt_stop	 305
12.28.1.16kpt_show_ui_sequence_key	 305
12.28.1.17kpt_show_ui_sequence_number	 305
12.28.1.18kpt_pattern_edit	 305
12.28.1.19kpt_event_edit	 305
12.28.1.20kpt_tap_bpm	 305
12.28.1.21kpt_pause	 305
12.28.1.22kpt_song_mode	 306
12.28.1.23kpt_toggle_jack	 306
12.28.1.24kpt_menu_mode	 306
12.28.1.25kpt_follow_transport	 306
12.28.1.26kpt_fast_forward	 306
12.28.1.27kpt_rewind	 306
12.28.1.28kpt_pointer_position	 306
12.28.1.29kpt_toggle_mutes	 306
12.29seq64::keystroke Class Reference	 306
12.29.1 Detailed Description	 307
12.29.2 Constructor & Destructor Documentation	 308

XIIV CONTENTS

12.29.2.1 keystroke() [1/3]	80
12.29.2.2 keystroke() [2/3]	80
12.29.2.3 keystroke() [3/3]	80
12.29.3 Member Function Documentation	80
12.29.3.1 operator=()	80
12.29.3.2 is_press()	09
12.29.3.3 is_letter()	09
12.29.3.4 is()	09
12.29.3.5 is_delete()	09
12.29.3.6 key()	09
12.29.3.7 shift_lock()	10
12.29.3.8 modifier()	10
12.29.3.9 mod_control()	10
12.29.3.10mod_control_shift()	10
12.29.3.11mod_super()	10
12.29.4 Field Documentation	10
12.29.4.1 m_is_press	10
12.29.4.2 m_key	10
12.29.4.3 m_modifier	11
12.30seq64::lash Class Reference	11
12.30.1 Detailed Description	11
12.30.2 Constructor & Destructor Documentation	12
12.30.2.1 lash()	12
12.30.3 Member Function Documentation	12
12.30.3.1 set_alsa_client_id()	12
12.30.3.2 start()	12
12.30.3.3 process_events()	12
12.30.3.4 init()	12
12.30.3.5 handle_event()	12
12.30.3.6 handle_config()	13

CONTENTS xlv

12.30.4 Field Documentation	313
12.30.4.1 m perform	313
12.30.4.2 m client	
12.30.4.3 m_lash_args	
12.30.4.4 m is lash supported	
12.31 seq64::lfownd Class Reference	
12.31.1 Detailed Description	
12.31.2 Constructor & Destructor Documentation	
12.31.2.1 Ifownd()	
12.31.2.2 ~lfownd()	
12.31.3 Member Function Documentation	
12.31.3.1 toggle_visible()	15
12.31.3.2 scale_lfo_change()	16
12.31.3.3 on_focus_out_event()	16
12.31.4 Field Documentation	16
12.31.4.1 m_seq	16
12.31.4.2 m_seqdata	16
12.31.4.3 m_hbox	16
12.31.4.4 m_scale_value	16
12.31.4.5 m_scale_range	16
12.31.4.6 m_scale_speed	116
12.31.4.7 m_scale_phase	116
12.31.4.8 m_scale_wave	316
12.31.4.9 m_value	317
12.31.4.10m_range	317
12.31.4.11m_speed	317
12.31.4.12m_phase	317
12.31.4.13m_wave	317
12.32seq64::maintime Class Reference	317
12.32.1 Detailed Description	319

XIVI CONTENTS

	12.32.2 Constructor & Destructor Documentation	320
	12.32.2.1 maintime() [1/2]	320
	12.32.2.2 maintime() [2/2]	320
	12.32.2.3 ~maintime()	320
	12.32.3 Member Function Documentation	320
	12.32.3.1 operator=()	320
	12.32.3.2 idle_progress()	320
	12.32.3.3 on_realize()	320
	12.32.3.4 on_expose_event()	321
	12.32.4 Friends And Related Function Documentation	321
	12.32.4.1 mainwnd	321
	12.32.5 Field Documentation	321
	12.32.5.1 m_beat_width	321
	12.32.5.2 m_bar_width	321
	12.32.5.3 m_pill_width	321
	12.32.5.4 m_box_width	321
	12.32.5.5 m_box_height	322
	12.32.5.6 m_flash_width	322
	12.32.5.7 m_flash_height	322
	12.32.5.8 m_flash_x	322
	12.32.5.9 m_box_less_pill	322
	12.32.5.10m_tick	322
	12.32.5.11m_ppqn	322
12.33	seq64::mainwid Class Reference	323
	12.33.1 Detailed Description	326
	12.33.2 Constructor & Destructor Documentation	326
	12.33.2.1 mainwid()	326
	12.33.2.2 ~mainwid()	326
	12.33.3 Member Function Documentation	327
	12.33.3.1 set_screenset()	327

CONTENTS xlvii

	12.33.3.2 reset()	327
	12.33.3.3 update_sequences_on_window()	327
	12.33.3.4 draw_pixmap_on_window()	327
	12.33.3.5 fill_background_window()	327
	12.33.3.6 redraw()	327
	12.33.3.7 seq_set_and_edit()	328
	12.33.3.8 seq_set_and_eventedit()	328
	12.33.3.9 draw_marker_on_sequence()	328
	12.33.3.10update_markers()	328
	12.33.3.11valid_sequence()	329
	12.33.3.12draw_sequence_on_pixmap()	329
	12.33.3.13draw_sequences_on_pixmap()	329
	12.33.3.14draw_sequence_pixmap_on_window()	330
	12.33.3.15seq_from_xy()	330
	12.33.3.16(imeout()	330
	12.33.3.17calculate_base_sizes()	330
	12.33.3.18select_fg_bg_colors()	331
	12.33.3.19on_realize()	331
	12.33.3.20on_expose_event()	331
	12.33.3.21on_button_press_event()	331
	12.33.3.22on_button_release_event()	332
	12.33.3.23on_motion_notify_event()	332
	12.33.3.24on_focus_in_event()	333
	12.33.3.25on_focus_out_event()	333
12.33.4	Friends And Related Function Documentation	333
	12.33.4.1 mainwnd	333
	12.33.4.2 update_mainwid_sequences	333
12.33.5	Field Documentation	333
	12.33.5.1 m_moving_seq	333
	12.33.5.2 m_button_down	334

xlviii CONTENTS

12.33.5.3 m_moving	334
12.33.5.4 m_old_seq	334
12.33.5.5 m_screenset	334
12.33.5.6 m_last_tick_x	334
12.33.5.7 m_last_playing	334
12.33.5.8 m_mainwnd_rows	334
12.33.5.9 m_mainwnd_cols	334
12.33.5.10m_seqarea_x	334
12.33.5.11m_seqarea_y	335
12.33.5.12m_seqarea_seq_x	335
12.33.5.13m_seqarea_seq_y	335
12.33.5.14m_mainwid_x	335
12.33.5.15m_mainwid_y	335
12.33.5.16m_mainwid_border	335
12.33.5.17m_mainwid_spacing	335
12.33.5.18m_text_size_x	335
12.33.5.19m_text_size_y	335
12.33.5.20m_max_sets	335
12.33.5.21m_screenset_slots	336
12.33.5.22m_screenset_offset	336
12.33.5.23m_progress_height	336
12.34seq64::mainwnd Class Reference	336
12.34.1 Constructor & Destructor Documentation	341
12.34.1.1 mainwnd()	341
12.34.1.2 ~mainwnd()	342
12.34.2 Member Function Documentation	342
12.34.2.1 open_file()	342
12.34.2.2 ppqn() [1/2]	342
12.34.2.3 ppqn() [2/2]	342
12.34.2.4 handle_signal()	342

CONTENTS xlix

12.34.2.5 adj_callback_ss()
12.34.2.6 adj_callback_bpm()
12.34.2.7 edit_callback_notepad()
12.34.2.8 timer_callback()
12.34.2.9 set_play_image()
12.34.2.10set_songlive_image()
12.34.2.11start_playing()
12.34.2.12pause_playing()
12.34.2.13stop_playing()
12.34.2.14toggle_playing()
12.34.2.15earn_toggle()
12.34.2.16open_performance_edit()
12.34.2.17open_performance_edit_2()
12.34.2.1&enregister_perfedits()
12.34.2.19sequence_key()
12.34.2.20apply_song_transpose()
12.34.2.21update_window_title()
12.34.2.22oLower()
12.34.2.23file_new()
12.34.2.24file_open()
12.34.2.25 ile_save()
12.34.2.26set_song_mute()
12.34.2.27file_import_dialog()
12.34.2.2&ptions_dialog()
12.34.2.29about_dialog()
12.34.2.30build_info_dialog()
12.34.2.31query_save_changes()
12.34.2.32new_open_error_dialog()
12.34.2.33file_save_as()
12.34.2.34file_exit()

I CONTENTS

	12.34.2.35new_file()	348
	12.34.2.36save_file()	348
	12.34.2.37choose_file()	348
	12.34.2.38s_save()	348
	12.34.2.39nstall_signal_handlers()	348
	12.34.2.40signal_action()	348
	12.34.2.41edit_field_has_focus()	349
	12.34.2.42on_delete_event()	349
	12.34.2.43on_key_press_event()	349
	12.34.2.44on_key_release_event()	349
	12.34.2.45on_grouplearnchange()	349
12.34.3	Field Documentation	350
	12.34.3.1 m_sigpipe	350
	12.34.3.2 m_tooltips	350
	12.34.3.3 m_menubar	350
	12.34.3.4 m_menu_file	350
	12.34.3.5 m_menu_edit	350
	12.34.3.6 m_menu_view	350
	12.34.3.7 m_menu_help	350
	12.34.3.8 m_ppqn	350
	12.34.3.9 m_main_wid	351
	12.34.3.10m_main_time	351
	12.34.3.11m_perf_edit	351
	12.34.3.12m_perf_edit_2	351
	12.34.3.13m_options	351
	12.34.3.14m_main_cursor	351
	12.34.3.15m_image_play	351
	12.34.3.16m_button_learn	351
	12.34.3.17m_button_stop	351
	12.34.3.18m_button_play	352

12.34.3.19m_button_perfedit	 352
12.34.3.20m_adjust_bpm	 352
12.34.3.21m_spinbutton_bpm	 352
12.34.3.22m_adjust_ss	 352
12.34.3.23m_spinbutton_ss	 352
12.34.3.24m_adjust_load_offset	 352
12.34.3.25m_spinbutton_load_offset	 352
12.34.3.20m_entry_notes	 353
12.34.3.27m_is_running	 353
12.34.3.28m_timeout_connect	 353
12.34.3.29m_menu_mode	 353
12.34.3.30m_call_seq_edit	 353
12.34.3.31m_call_seq_eventedit	 353
12.35seq64::mastermidibus Class Reference	 353
12.35.1 Constructor & Destructor Documentation	 356
12.35.1.1 mastermidibus()	 356
12.35.1.2 ~mastermidibus()	 356
12.35.2 Member Function Documentation	 357
12.35.2.1 init()	 357
12.35.2.2 get_alsa_seq()	 357
12.35.2.3 get_num_out_buses()	 357
12.35.2.4 get_num_in_buses()	 357
12.35.2.5 set_beats_per_minute()	 357
12.35.2.6 set_ppqn()	 357
12.35.2.7 filter_by_channel() [1/2]	 358
12.35.2.8 filter_by_channel() [2/2]	 358
12.35.2.9 get_beats_per_minute()	 358
12.35.2.10get_ppqn()	 358
12.35.2.11get_midi_out_bus_name()	 358
12.35.2.12get_midi_in_bus_name()	 359

lii CONTENTS

	12.35.2.13print()	359
	12.35.2.14flush()	359
	12.35.2.15start()	359
	12.35.2.16stop()	359
	12.35.2.17clock()	359
	12.35.2.1&ontinue_from()	360
	12.35.2.19nit_clock()	360
	12.35.2.20poll_for_midi()	360
	12.35.2.21is_more_input()	360
	12.35.2.22get_midi_event()	361
	12.35.2.23set_sequence_input()	361
	12.35.2.24dump_midi_input()	361
	12.35.2.25s_dumping()	361
	12.35.2.26get_sequence()	362
	12.35.2.27sysex()	362
	12.35.2.2&port_start()	362
	12.35.2.29port_exit()	362
	12.35.2.30play()	363
	12.35.2.31set_clock()	363
	12.35.2.32get_clock()	363
	12.35.2.33set_input()	363
	12.35.2.34get_input()	364
12.35.3	Field Documentation	364
	12.35.3.1 m_alsa_seq	364
	12.35.3.2 m_max_busses	364
	12.35.3.3 m_num_out_buses	364
	12.35.3.4 m_num_in_buses	364
	12.35.3.5 m_buses_out	364
	12.35.3.6 m_buses_in	365
	12.35.3.7 m_bus_announce	365

12.35.3.8 m_buses_out_active	365
12.35.3.9 m_buses_in_active	365
12.35.3.10m_buses_out_init	365
12.35.3.11m_buses_in_init	365
12.35.3.12m_init_clock	365
12.35.3.13m_init_input	365
12.35.3.14m_queue	365
12.35.3.15m_ppqn	365
12.35.3.16m_beats_per_minute	366
12.35.3.17m_num_poll_descriptors	366
12.35.3.18m_poll_descriptors	366
12.35.3.19m_dumping_input	366
12.35.3.20m_vector_sequence	366
12.35.3.21m_filter_by_channel	366
12.35.3.22m_seq	366
12.35.3.23m_mutex	366
12.36seq64::midi_container Class Reference	367
12.36.1 Detailed Description	369
12.36.2 Constructor & Destructor Documentation	369
12.36.2.1 midi_container()	369
12.36.2.2 ~midi_container()	369
12.36.3 Member Function Documentation	369
12.36.3.1 fill()	369
12.36.3.2 size()	370
12.36.3.3 done()	370
12.36.3.4 put()	370
12.36.3.5 get()	371
12.36.3.6 clear()	371
12.36.3.7 position_reset()	371
12.36.3.8 position()	371

liv CONTENTS

12.36.3.9 position_increment()
12.36.3.10add_variable()
12.36.3.11add_long()
12.36.3.12add_short()
12.36.3.13add_event()
12.36.3.14fill_seq_number()
12.36.3.15fill_seq_name()
12.36.3.16fill_meta_track_end()
12.36.3.17/ill_proprietary()
12.36.3.18fill_time_sig_and_tempo()
12.36.3.19song_fill_seq_event()
12.36.3.20song_fill_seq_trigger()
12.36.4 Friends And Related Function Documentation
12.36.4.1 midifile
12.36.5 Field Documentation
12.36.5.1 m_sequence
12.36.5.2 m_position_for_get
12.37seq64::midi_control Class Reference
12.37.1 Detailed Description
12.37.2 Constructor & Destructor Documentation
12.37.2.1 midi_control()
12.37.3 Member Function Documentation
12.37.3.1 active()
12.37.3.2 inverse_active()
12.37.3.3 status()
12.37.3.4 data()
12.37.3.5 min_value()
12.37.3.6 max_value()
12.37.3.7 set() [1/2]
12.37.3.8 set() [2/2]

12.37.3.9 match()	377
12.37.3.10n_range()	377
12.37.4 Field Documentation	377
12.37.4.1 m_active	377
12.37.4.2 m_inverse_active	377
12.37.4.3 m_status	378
12.37.4.4 m_data	378
12.37.4.5 m_min_value	378
12.37.4.6 m_max_value	378
12.38seq64::midi_list Class Reference	378
12.38.1 Member Typedef Documentation	380
12.38.1.1 CharList	380
12.38.2 Constructor & Destructor Documentation	380
12.38.2.1 midi_list()	380
12.38.2.2 ~midi_list()	380
12.38.3 Member Function Documentation	381
12.38.3.1 size()	381
12.38.3.2 done()	381
12.38.3.3 put()	381
12.38.3.4 get()	381
12.38.3.5 clear()	381
12.38.4 Field Documentation	381
12.38.4.1 m_char_list	381
12.39seq64::midi_measures Class Reference	382
12.39.1 Detailed Description	382
12.39.2 Constructor & Destructor Documentation	382
12.39.2.1 midi_measures() [1/2]	382
12.39.2.2 midi_measures() [2/2]	382
12.39.3 Member Function Documentation	383
12.39.3.1 measures() [1/2]	383

Ivi CONTENTS

12.39.3.2 measures() [2/2]	383
12.39.3.3 beats() [1/2]	383
12.39.3.4 beats() [2/2]	383
12.39.3.5 divisions() [1/2]	383
12.39.3.6 divisions() [2/2]	383
12.39.4 Field Documentation	384
12.39.4.1 m_measures	384
12.39.4.2 m_beats	384
12.39.4.3 m_divisions	384
12.40seq64::midi_splitter Class Reference	384
12.40.1 Detailed Description	385
12.40.2 Constructor & Destructor Documentation	385
12.40.2.1 midi_splitter()	385
12.40.2.2 ~midi_splitter()	386
12.40.3 Member Function Documentation	386
12.40.3.1 log_main_sequence()	386
12.40.3.2 initialize()	386
12.40.3.3 increment()	386
12.40.3.4 split()	386
12.40.3.5 ppqn()	387
12.40.3.6 count()	387
12.40.3.7 split_channel()	387
12.40.4 Field Documentation	388
12.40.4.1 m_ppqn	388
12.40.4.2 m_use_default_ppqn	388
12.40.4.3 m_smf0_channels_count	388
12.40.4.4 m_smf0_channels	388
12.40.4.5 m_smf0_main_sequence	388
12.40.4.6 m_smf0_seq_number	388
12.41seq64::midi_timing Class Reference	388

12.41.1 Detailed Description	. 389
12.41.2 Constructor & Destructor Documentation	. 389
12.41.2.1 midi_timing() [1/2]	. 389
12.41.2.2 midi_timing() [2/2]	. 389
12.41.3 Member Function Documentation	. 390
12.41.3.1 beats_per_minute() [1/2]	. 390
12.41.3.2 beats_per_minute() [2/2]	. 390
12.41.3.3 beats_per_measure() [1/2]	. 390
12.41.3.4 beats_per_measure() [2/2]	. 390
12.41.3.5 beat_width() [1/2]	. 390
12.41.3.6 beat_width() [2/2]	. 390
12.41.3.7 ppqn() [1/2]	. 391
12.41.3.8 ppqn() [2/2]	. 391
12.41.4 Field Documentation	. 391
12.41.4.1 m_beats_per_minute	. 391
12.41.4.2 m_beats_per_measure	. 391
12.41.4.3 m_beat_width	. 391
12.41.4.4 m_ppqn	. 391
12.42seq64::midi_vector Class Reference	. 392
12.42.1 Member Typedef Documentation	. 393
12.42.1.1 CharVector	. 393
12.42.2 Constructor & Destructor Documentation	. 393
12.42.2.1 midi_vector()	. 393
12.42.2.2 ~midi_vector()	. 393
12.42.3 Member Function Documentation	. 394
12.42.3.1 size()	. 394
12.42.3.2 done()	. 394
12.42.3.3 put()	. 394
12.42.3.4 get()	. 394
12.42.3.5 clear()	. 395

Iviii CONTENTS

12.42.4 Field Documentation	395
12.42.4.1 m_char_vector	395
12.43seq64::midibus Class Reference	395
12.43.1 Constructor & Destructor Documentation	397
12.43.1.1 midibus() [1/2]	397
12.43.1.2 midibus() [2/2]	398
12.43.1.3 ~midibus()	398
12.43.2 Member Function Documentation	398
12.43.2.1 init_out()	398
12.43.2.2 init_in()	398
12.43.2.3 deinit_in()	398
12.43.2.4 init_out_sub()	399
12.43.2.5 init_in_sub()	399
12.43.2.6 print()	399
12.43.2.7 get_name()	399
12.43.2.8 get_id()	399
12.43.2.9 play()	399
12.43.2.10sysex()	399
12.43.2.11start()	400
12.43.2.12stop()	400
12.43.2.13clock()	400
12.43.2.14continue_from()	400
12.43.2.15nit_clock()	400
12.43.2.16set_clock()	401
12.43.2.17get_clock()	401
12.43.2.18set_input()	401
12.43.2.19get_input()	401
12.43.2.20flush()	401
12.43.2.21get_client()	401
12.43.2.22get_port()	401

-01
-02
02
02
-02
02
02
02
02
02
02
-03
-03
-03
-03
-03
-03
-03
-03
-03
-06
-06
-06
-07
-07
07
-08
.09
.09
-09

IX

12.44.3.6 ppqn()
12.44.3.7 parse_smf_0()
12.44.3.8 parse_smf_1()
12.44.3.9 parse_prop_header()
12.44.3.10parse_proprietary_track()
12.44.3.11pow2()
12.44.3.12checklen()
12.44.3.13add_trigger()
12.44.3.14read_long()
12.44.3.15read_short()
12.44.3.16read_byte()
12.44.3.17read_varinum()
12.44.3.18write_long()
12.44.3.19write_short()
12.44.3.20read_byte_array()
12.44.3.21write_byte()
12.44.3.22write_varinum()
12.44.3.23write_track_name()
12.44.3.24read_track_name()
12.44.3.25write_seq_number()
12.44.3.26read_seq_number()
12.44.3.27write_track_end()
12.44.3.28write_header()
12.44.3.29write_prop_header()
12.44.3.30write_proprietary_track()
12.44.3.31varinum_size()
12.44.3.32prop_item_size()
12.44.3.33track_name_size()
12.44.3.34errdump() [1/2]
12.44.3.35errdump() [2/2]

12.44.3.36write_track()	420
12.44.3.37seq_number_size()	420
12.44.3.3&track_end_size()	420
12.44.3.39s_sysex_special_id()	420
12.44.4 Field Documentation	420
12.44.4.1 m_mutex	420
12.44.4.2 m_file_size	421
12.44.4.3 m_error_message	421
12.44.4.4 m_error_is_fatal	421
12.44.4.5 m_disable_reported	421
12.44.4.6 m_pos	421
12.44.4.7 m_name	421
12.44.4.8 m_data	421
12.44.4.9 m_char_list	422
12.44.4.10m_new_format	422
12.44.4.11m_global_bgsequence	422
12.44.4.12m_ppqn	422
12.44.4.13m_use_default_ppqn	422
12.44.4.14m_smf0_splitter	422
12.45seq64::mutex Class Reference	423
12.45.1 Constructor & Destructor Documentation	424
12.45.1.1 mutex()	424
12.45.2 Member Function Documentation	424
12.45.2.1 lock()	424
12.45.2.2 unlock()	424
12.45.3 Field Documentation	424
12.45.3.1 sm_recursive_mutex	424
12.45.3.2 m_mutex_lock	424
12.46seq64::editable_event::name_value_t Struct Reference	424
12.46.1 Field Documentation	425

lxii CONTENTS

12.46.1.1 event_value	25
12.46.1.2 event_name	25
12.47seq64::options Class Reference	25
12.47.1 Member Enumeration Documentation	26
12.47.1.1 button	26
12.47.2 Constructor & Destructor Documentation	27
12.47.2.1 options()	27
12.47.3 Member Function Documentation	27
12.47.3.1 perf()	27
12.47.3.2 clock_callback_off()	27
12.47.3.3 clock_callback_on()	27
12.47.3.4 clock_callback_mod()	27
12.47.3.5 clock_mod_callback()	27
12.47.3.6 input_callback()	27
12.47.3.7 filter_callback()	28
12.47.3.8 transport_callback()	28
12.47.3.9 mouse_seq24_callback()	28
12.47.3.10mouse_fruity_callback()	28
12.47.3.11mouse_mod4_callback()	28
12.47.3.12mouse_snap_split_callback()	28
12.47.3.13ash_support_callback()	28
12.47.3.14add_midi_clock_page()	28
12.47.3.15add_midi_input_page()	28
12.47.3.16add_keyboard_page()	29
12.47.3.17add_extended_keys_page()	29
12.47.3.18add_mouse_page()	29
12.47.3.19add_jack_sync_page()	29
12.47.4 Field Documentation	29
12.47.4.1 m_tooltips	29
12.47.4.2 m_mainperf	29

12.47.4.3 m_button_ok	 429
12.47.4.4 m_button_jack_transport	 429
12.47.4.5 m_button_jack_master	 429
12.47.4.6 m_button_jack_master_cond	 429
12.47.4.7 m_button_jack_connect	 430
12.47.4.8 m_button_jack_disconnect	 430
12.47.4.9 m_notebook	 430
12.48seq64::optionsfile Class Reference	 430
12.48.1 Detailed Description	 431
12.48.2 Constructor & Destructor Documentation	 431
12.48.2.1 optionsfile()	 431
12.48.2.2 ~optionsfile()	 431
12.48.3 Member Function Documentation	 431
12.48.3.1 parse()	 431
12.48.3.2 write()	 433
12.48.3.3 error_message()	 434
12.49seq64::perfedit Class Reference	 434
12.49.1 Detailed Description	 439
12.49.2 Constructor & Destructor Documentation	 439
12.49.2.1 perfedit()	 439
12.49.2.2 ~perfedit()	 440
12.49.3 Member Function Documentation	 440
12.49.3.1 init_before_show()	 440
12.49.3.2 enqueue_draw()	 440
12.49.3.3 zoom_check()	 440
12.49.3.4 enregister_peer()	 440
12.49.3.5 set_zoom()	 441
12.49.3.6 get_toggle_jack()	 441
12.49.3.7 toggle_jack()	 441
12.49.3.8 rewind()	 441
·=····································	

lxiv CONTENTS

12	2.49.3.9 fast_forward()	441
12	.49.3.10set_follow_transport()	441
12	49.3.1 ttoggle_follow_transport()	442
12	49.3.12set_jack_mode()	442
12	2.49.3.13set_transpose()	442
12	2.49.3.14transpose_button_callback()	442
12	2.49.3.15set_beats_per_bar()	442
12	2.49.3.16set_beat_width()	443
12	2.49.3.17set_snap()	443
12	2.49.3.18set_guides()	443
12	2.49.3.19grow()	443
12	2.49.3.20set_looped()	443
12	.49.3.21expand()	443
12	2.49.3.22collapse()	444
12	.49.3.23copy()	444
12	.49.3.24undo()	444
12	.49.3.25redo()	444
12	2.49.3.26popup_menu()	444
12	2.49.3.27draw_sequences()	444
12	.49.3.28imeout()	444
12	.49.3.29set_image()	444
12	.49.3.30start_playing()	445
12	.49.3.31pause_playing()	445
12	.49.3.32stop_playing()	445
12	.49.3.33toggle_playing()	445
12	.49.3.34on_realize()	445
12	.49.3.35on_key_press_event()	445
12	.49.3.36on_delete_event()	446
12.49.4 Fri	iends And Related Function Documentation	446
12	.49.4.1 update_perfedit_sequences	446

12.49.4.2 FF_RW_timeout
12.49.5 Field Documentation
12.49.5.1 m_peer_perfedit
12.49.5.2 m_table
12.49.5.3 m_vadjust
12.49.5.4 m_hadjust
12.49.5.5 m_vscroll
12.49.5.6 m_hscroll
12.49.5.7 m_perfnames
12.49.5.8 m_perfroll
12.49.5.9 m_perftime
12.49.5.10m_menu_snap
12.49.5.11m_menu_xpose
12.49.5.12m_button_xpose
12.49.5.13m_entry_xpose
12.49.5.14m_image_play
12.49.5.15m_button_snap
12.49.5.16m_entry_snap
12.49.5.17m_button_stop
12.49.5.18m_button_play
12.49.5.19m_button_loop
12.49.5.20m_button_expand
12.49.5.21m_button_collapse
12.49.5.22m_button_copy
12.49.5.23m_button_grow
12.49.5.24m_button_undo
12.49.5.25m_button_redo
12.49.5.26m_button_jack
12.49.5.27m_button_follow
12.49.5.28m_button_bpm

lxvi CONTENTS

12.49.5.29m_entry_bpm	149
12.49.5.30m_button_bw	149
12.49.5.31m_entry_bw	149
12.49.5.32m_hbox	149
12.49.5.33m_hlbox	ŀ50
12.49.5.34m_tooltips	ŀ50
12.49.5.35m_menu_bpm	ŀ50
12.49.5.36m_menu_bw	ŀ50
12.49.5.37m_snap	ŀ50
12.49.5.38m_bpm	ŀ50
12.49.5.39m_bw	ŀ50
12.49.5.40m_ppqn	ŀ50
12.49.5.41m_is_running	ŀ50
12.49.5.42m_standard_bpm	ŀ51
12.50seq64::perfnames Class Reference	ŀ51
12.50.1 Detailed Description	ŀ53
12.50.2 Constructor & Destructor Documentation	ŀ53
12.50.2.1 perfnames()	ŀ53
12.50.2.2 ~perfnames()	ŀ54
12.50.3 Member Function Documentation	ŀ54
12.50.3.1 redraw_dirty_sequences()	ŀ54
12.50.3.2 enqueue_draw()	ŀ54
12.50.3.3 convert_y()	ŀ54
12.50.3.4 draw_sequences()	ŀ54
12.50.3.5 draw_sequence()	ŀ54
12.50.3.6 change_vert()	ŀ55
12.50.3.7 redraw()	ŀ55
12.50.3.8 on_realize()	ŀ55
12.50.3.9 on_expose_event()	ŀ55
12.50.3.10on_button_press_event()	ŀ56

12.50.3.11on_button_release_event()	 456
12.50.3.12on_size_allocate()	 456
12.50.3.13on_scroll_event()	 457
12.50.4 Friends And Related Function Documentation	 457
12.50.4.1 perfedit	 457
12.50.5 Field Documentation	 457
12.50.5.1 m_parent	 457
12.50.5.2 m_names_chars	 457
12.50.5.3 m_char_w	 457
12.50.5.4 m_setbox_w	 458
12.50.5.5 m_namebox_w	 458
12.50.5.6 m_names_x	 458
12.50.5.7 m_names_y	 458
12.50.5.8 m_xy_offset	 458
12.50.5.9 m_seqs_in_set	 458
12.50.5.10m_sequence_max	 458
12.50.5.11m_sequence_offset	 458
12.50.5.12m_sequence_active	 459
2.51 seq64::perform Class Reference	 459
12.51.1 Detailed Description	 471
12.51.2 Member Enumeration Documentation	 471
12.51.2.1 mute_op_t	 471
12.51.2.2 ff_rw_button_t	 471
12.51.3 Constructor & Destructor Documentation	 472
12.51.3.1 perform()	 472
12.51.3.2 ~perform()	 472
12.51.4 Member Function Documentation	 472
12.51.4.1 is_modified() [1/2]	 472
12.51.4.2 modify()	 472
12.51.4.3 sequence_count()	 472

Ixviii CONTENTS

12.51.4.4 sequence_max()
12.51.4.5 is_control_status()
12.51.4.6 set_edit_sequence()
12.51.4.7 unset_edit_sequence()
12.51.4.8 is_edit_sequence()
12.51.4.9 get_beats_per_bar()
12.51.4.10set_beats_per_bar()
12.51.4.11get_beat_width()
12.51.4.12set_beat_width()
12.51.4.13clocks_per_metronome() [1/2]
12.51.4.14clocks_per_metronome() [2/2]
12.51.4.15set_32nds_per_quarter()
12.51.4.16get_32nds_per_quarter()
12.51.4.17us_per_quarter_note() [1/2]
12.51.4.1&us_per_quarter_note() [2/2]
12.51.4.19gui() [1/2]
12.51.4.20gui() [2/2]
12.51.4.21keys() [1/2]
12.51.4.22keys() [2/2]
12.51.4.23master_bus()
12.51.4.24filter_by_channel()
12.51.4.25s_running()
12.51.4.26s_pattern_playing() [1/2]
12.51.4.27toggle_song_start_mode()
12.51.4.28song_start_mode() [1/2]
12.51.4.29song_start_mode() [2/2]
12.51.4.30s_jack_running()
12.51.4.31is_jack_master()
12.51.4.32enregister()
12.51.4.33toggle_jack_mode()

12.51.4.34set_jack_mode()
12.51.4.35get_toggle_jack()
12.51.4.36set_jack_stop_tick()
12.51.4.37combine_bytes()
12.51.4.38FF_rewind()
12.51.4.39FF_RW_timeout()
12.51.4.40start_from_perfedit() [1/2]
12.51.4.41start_from_perfedit() [2/2]
12.51.4.42set_follow_transport()
12.51.4.43get_follow_transport()
12.51.4.44toggle_follow_transport()
12.51.4.45set_reposition()
12.51.4.46f_rw_type() [1/2]
12.51.4.47f_rw_type() [2/2]
12.51.4.48rewind()
12.51.4.49fast_forward()
12.51.4.50reposition()
12.51.4.51clear_all()
12.51.4.52aunch()
12.51.4.53new_sequence()
12.51.4.54add_sequence()
12.51.4.55delete_sequence()
12.51.4.56s_sequence_in_edit()
12.51.4.57clear_sequence_triggers()
12.51.4.5\parint_triggers()
12.51.4.59finish()
12.51.4.60get_tick()
12.51.4.61get_jack_tick()
12.51.4.62set_jack_tick()
12.51.4.63set_left_tick()

IXX CONTENTS

12.51.4.64get_left_tick()
12.51.4.65set_start_tick()
12.51.4.66get_start_tick()
12.51.4.67set_right_tick()
12.51.4.6&get_right_tick()
12.51.4.69eft_right_size()
12.51.4.70s_active()
12.51.4.71apply_song_transpose()
12.51.4.72set_transpose()
12.51.4.73get_transpose()
12.51.4.74get_beats_per_minute()
12.51.4.75set_sequence_control_status()
12.51.4.7@unset_sequence_control_status()
12.51.4.77sequence_playing_toggle()
12.51.4.78sequence_playing_change()
12.51.4.79sequence_playing_on()
12.51.4.80sequence_playing_off()
12.51.4.81mute_all_tracks()
12.51.4.82oggle_all_tracks()
12.51.4.83armed_saved()
12.51.4.84toggle_playing_tracks()
12.51.4.85mute_screenset()
12.51.4.8@utput_func()
12.51.4.87input_func()
12.51.4.88set_group_mute_state()
12.51.4.89get_group_mute_state()
12.51.4.90set_offset()
12.51.4.91get_offset()
12.51.4.92save_playing_state()
12.51.4.93restore_playing_state()

12.51.4.94key_name()
12.51.4.95get_key_events()
12.51.4.96get_key_groups()
12.51.4.97get_key_events_rev()
12.51.4.98get_key_groups_rev()
12.51.4.99show_ui_sequence_key() [1/2]
12.51.4.108how_ui_sequence_key() [2/2]
12.51.4.10show_ui_sequence_number() [1/2]
12.51.4.102how_ui_sequence_number() [2/2]
12.51.4.10@lokup_keyevent_key()
12.51.4.104okup_keyevent_seq()
12.51.4.10 5 okup_keygroup_key()
12.51.4.10 6 okup_keygroup_group()
12.51.4.10start_playing()
12.51.4.10 <u>Mause_playing()</u>
12.51.4.10\(\text{Q}\) op_playing()
12.51.4.11start_key()
12.51.4.11plause_key()
12.51.4.11s2op_key()
12.51.4.11l@arn_toggle()
12.51.4.11decrement_beats_per_minute()
12.51.4.11iācrement_beats_per_minute()
12.51.4.11@crement_screenset()
12.51.4.11in crement_screenset()
12.51.4.11Maghlight()
12.51.4.11i9_smf_0()
12.51.4.120et_sequence() [1/2]
12.51.4.12get_sequence() [2/2] 495
12.51.4.123equence_key()
12.51.4.12Sequence_label()

Ixxii CONTENTS

12.51.4.12s/et_input_bus()
12.51.4.125nainwnd_key_event()
12.51.4.12@crfroll_key_event()
12.51.4.12p7ayback_key_event()
12.51.4.128aove_triggers()
12.51.4.129py_triggers()
12.51.4.13 <u>push_trigger_undo()</u>
12.51.4.13plop_trigger_undo()
12.51.4.13p2op_trigger_redo()
12.51.4.138_dirty_main()
12.51.4.1 36_ dirty_edit()
12.51.4.135_dirty_perf()
12.51.4.136_dirty_names()
12.51.4.13\(\overline{3}\)_exportable()
12.51.4.13 <u>8</u> et_screenset()
12.51.4.139et_screenset()
12.51.4.14@et_playing_screenset()
12.51.4.14flave_undo()
12.51.4.14&et_have_undo()
12.51.4.14@ave_redo()
12.51.4.14set_have_redo()
12.51.4.145plit_trigger()
12.51.4.14@et_max_trigger()
12.51.4.14 0 ollapse()
12.51.4.14@bpy()
12.51.4.14@xpand()
12.51.4.15@idi_control_toggle()
12.51.4.15rhidi_control_on()
12.51.4.1522idi_control_off()
12.51.4.150andle_midi_control()

12.51.4.15glet_screen_set_notepad()
12.51.4.155urrent_screen_set_notepad()
12.51.4.15@et_screen_set_notepad() [1/2]
12.51.4.155et_screen_set_notepad() [2/2]
12.51.4.15&et_playing_screenset()
12.51.4.15@ny_group_unmutes()
12.51.4.16@nute_group_tracks()
12.51.4.16delect_and_mute_group()
12.51.4.16&et_song_mute()
12.51.4.16%et_mode_group_mute()
12.51.4.164Inset_mode_group_mute()
12.51.4.16 Select_group_mute()
12.51.4.16 Set_mode_group_learn()
12.51.4.16\(\overline{U}\)nset_mode_group_learn()
12.51.4.168_group_learning()
12.51.4.16 <u>Set_and_copy_mute_group()</u>
12.51.4.17start()
12.51.4.17stop()
12.51.4.17start_jack()
12.51.4.17\(\frac{1}{2}\) top_jack()
12.51.4.17plosition_jack()
12.51.4.176ff_sequences()
12.51.4.1761_notes_off()
12.51.4.17 s et_active()
12.51.4.17 % et_was_active()
12.51.4.17@set_sequences()
12.51.4.1 % മിay()
12.51.4.18slet_orig_ticks()
12.51.4.182et_beats_per_minute()
12.51.4.18Set_looping()

Ixxiv

12.51.4.18	 510
12.51.4.18 ā unch_input_thread()	 510
12.51.4.18@unch_output_thread()	 510
12.51.4.18nit_jack()	 510
12.51.4.1828einit_jack()	 510
12.51.4.189eq_in_playing_screen()	 510
12.51.4.196_modified() [2/2]	 511
12.51.4.19//alid_midi_control_seq()	 511
12.51.4.198_screenset_valid()	 511
12.51.4.19 & et_running()	 512
12.51.4.196_pattern_playing() [2/2]	 512
12.51.4.195et_playback_mode()	 512
12.51.4.19@ute_group_offset()	 512
12.51.4.198_seq_valid()	 512
12.51.4.198_mseq_valid()	 513
12.51.4.19@stall_sequence()	 513
12.51.4.200ner_start()	 514
12.51.4.2@finer_stop()	 514
12.51.4.2021amp_track()	 514
12.51.4.20 Set_all_key_events()	 515
12.51.4.20set_all_key_groups()	 515
12.51.4.20 Set_key_event()	 515
12.51.4.20 <u>set_key_group()</u>	 515
12.51.5 Friends And Related Function Documentation	 516
12.51.5.1 jack_assistant	 516
12.51.5.2 keybindentry	 516
12.51.5.3 mainwnd	 516
12.51.5.4 midifile	 516
12.51.5.5 optionsfile	 516
12.51.5.6 options	 516

12.51.5.7 perfedit	. 516
12.51.5.8 perfroll	. 516
12.51.5.9 input_thread_func	. 516
12.51.5.10output_thread_func	. 517
12.51.5.11jack_sync_callback	. 517
12.51.5.1\(\frac{1}{2}\)ack_process_callback	. 518
12.51.5.13ack_shutdown	. 518
12.51.5.14jack_timebase_callback	. 518
12.51.5.15get_current_jack_position	. 519
12.51.6 Field Documentation	. 519
12.51.6.1 sm_mc_dummy	. 519
12.51.6.2 m_song_start_mode	. 519
12.51.6.3 m_start_from_perfedit	. 520
12.51.6.4 m_reposition	. 520
12.51.6.5 m_excell_FF_RW	. 520
12.51.6.6 m_FF_RW_button_type	. 520
12.51.6.7 m_gui_support	. 520
12.51.6.8 m_mute_group	. 520
12.51.6.9 m_armed_saved	. 520
12.51.6.10m_armed_statuses	. 520
12.51.6.11m_tracks_mute_state	. 520
12.51.6.12m_mode_group	. 521
12.51.6.13m_mode_group_learn	. 521
12.51.6.14m_mute_group_selected	. 521
12.51.6.15m_playing_screen	. 521
12.51.6.16m_playscreen_offset	. 521
12.51.6.17m_seqs	. 521
12.51.6.18m_seqs_active	. 521
12.51.6.19m_was_active_main	. 522
12.51.6.20m_was_active_edit	. 522

lxxvi CONTENTS

12.51.6.21m_was_active_perf
12.51.6.22m_was_active_names
12.51.6.23m_sequence_state
12.51.6.24m_master_bus
12.51.6.25m_transpose
12.51.6.26m_out_thread
12.51.6.27m_in_thread
12.51.6.28m_out_thread_launched
12.51.6.29m_in_thread_launched
12.51.6.30m_running
12.51.6.31m_is_pattern_playing
12.51.6.32m_inputing
12.51.6.33m_outputing
12.51.6.34m_looping
12.51.6.35m_playback_mode
12.51.6.36m_ppqn
12.51.6.37m_beats_per_bar
12.51.6.38m_beat_width
12.51.6.39m_clocks_per_metronome
12.51.6.40m_32nds_per_quarter
12.51.6.41m_us_per_quarter_note
12.51.6.42m_one_measure
12.51.6.43m_left_tick
12.51.6.44m_right_tick
12.51.6.45m_starting_tick
12.51.6.46m_tick
12.51.6.47m_jack_tick
12.51.6.48m_usemidiclock
12.51.6.49m_midiclockrunning
12.51.6.50m_midiclocktick

12.51.6.51m_midiclockpos
12.51.6.52m_dont_reset_ticks
12.51.6.53m_screen_set_notepad
12.51.6.54m_midi_cc_toggle
12.51.6.55m_midi_cc_on
12.51.6.56m_midi_cc_off
12.51.6.57m_offset
12.51.6.58m_control_status
12.51.6.59m_screenset
12.51.6.60m_seqs_in_set
12.51.6.61m_max_sets
12.51.6.62m_sequence_count
12.51.6.63m_sequence_max
12.51.6.64m_edit_sequence
12.51.6.65m_is_modified
12.51.6.66m_condition_var
12.51.6.67m_jack_asst
12.51.6.68m_have_undo
12.51.6.69m_undo_vect
12.51.6.70m_have_redo
12.51.6.71m_redo_vect
12.51.6.72m_notify
12.52seq64::performcallback Struct Reference
12.52.1 Detailed Description
12.52.2 Member Function Documentation
12.52.2.1 on_grouplearnchange()
12.53seq64::perfroll Class Reference
12.53.1 Constructor & Destructor Documentation
12.53.1.1 perfroll()
12.53.1.2 ~perfroll()

Ixxviii CONTENTS

2.53.2	Member Function Documentation	535
	12.53.2.1 set_guides()	535
	12.53.2.2 update_sizes()	536
	12.53.2.3 init_before_show()	536
	12.53.2.4 fill_background_pixmap()	536
	12.53.2.5 increment_size()	536
	12.53.2.6 draw_all()	536
	12.53.2.7 follow_progress()	536
	12.53.2.8 redraw_progress()	537
	12.53.2.9 draw_progress()	537
	12.53.2.10redraw_dirty_sequences()	537
	12.53.2.11set_ppqn()	537
	12.53.2.12convert_xy()	537
	12.53.2.13convert_x()	538
	12.53.2.14snap_x()	538
	12.53.2.15draw_sequence_on()	538
	12.53.2.16draw_background_on()	538
	12.53.2.17draw_drawable_row()	539
	12.53.2.1&change_horz()	539
	12.53.2.19change_vert()	539
	12.53.2.20split_trigger()	539
	12.53.2.21enqueue_draw()	539
	12.53.2.2&et_zoom()	539
	12.53.2.23convert_drop_xy()	540
	12.53.2.24horizontal_adjust()	540
	12.53.2.25vertical_adjust()	541
	12.53.2.26horizontal_set()	541
	12.53.2.27vertical_set()	541
	12.53.2.28on_realize()	541
	12.53.2.29on_expose_event()	542

12.53.2.30on_button_press_event()	42
12.53.2.31on_button_release_event()	42
12.53.2.32on_motion_notify_event()	42
12.53.2.33on_scroll_event()	43
12.53.2.34on_focus_in_event()	43
12.53.2.35on_focus_out_event()	43
12.53.2.36on_size_allocate()	43
12.53.2.37on_key_press_event()	43
12.53.2.3&n_size_request()	44
12.53.3 Friends And Related Function Documentation	44
12.53.3.1 FruityPerfInput	44
12.53.3.2 Seq24PerfInput	44
12.53.3.3 perfedit	44
12.53.4 Field Documentation	44
12.53.4.1 m_parent	44
12.53.4.2 m_h_page_increment	44
12.53.4.3 m_v_page_increment	44
12.53.4.4 m_snap	45
12.53.4.5 m_ppqn	45
12.53.4.6 m_page_factor	45
12.53.4.7 m_divs_per_beat	45
12.53.4.8 m_ticks_per_bar	45
12.53.4.9 m_perf_scale_x	45
12.53.4.10m_zoom	45
12.53.4.11m_names_y	45
12.53.4.12m_background_x	45
12.53.4.13m_size_box_w	46
12.53.4.14m_measure_length	46
12.53.4.15m_beat_length	46
12.53.4.16m_old_progress_ticks	46

IXXX

16
16
16
16
17
17
! 7
17
! 7
! 7
! 7
18
18
18
18
18
18
19
51
51
52
52
52
52
52
52
3
3
3
3

12.54.2.9 change_horz()	553
12.54.2.10set_ppqn()	553
12.54.2.11tick_to_pixel()	554
12.54.2.12pixel_to_tick()	554
12.54.2.13tick_offset()	554
12.54.2.14update_sizes()	554
12.54.2.15dle_progress()	554
12.54.2.1@pdate_pixmap()	555
12.54.2.17draw_pixmap_on_window()	555
12.54.2.18on_realize()	555
12.54.2.19on_expose_event()	555
12.54.2.20on_button_press_event()	555
12.54.2.21on_size_allocate()	556
12.54.2.22on_button_release_event()	556
12.54.2.23key_press_event()	556
12.54.3 Friends And Related Function Documentation	557
12.54.3.1 perfedit	557
12.54.4 Field Documentation	557
12.54.4.1 m_parent	557
12.54.4.2 m_4bar_offset	557
12.54.4.3 m_tick_offset	557
12.54.4.4 m_ppqn	557
12.54.4.5 m_snap	557
12.54.4.6 m_measure_length	557
12.54.4.7 m_left_marker_tick	558
12.54.4.8 m_right_marker_tick	558
12.54.4.9 m_perf_scale_x	558
12.54.4.10m_timearea_y	558
12.55seq64::rc_settings Class Reference	558
12.55.1 Detailed Description	562

Ixxxii CONTENTS

12.55.2 Constructor & Destructor Documentation	562
12.55.2.1 rc_settings() [1/2]	562
12.55.2.2 rc_settings() [2/2]	562
12.55.3 Member Function Documentation	563
12.55.3.1 operator=()	563
12.55.3.2 config_filespec()	563
12.55.3.3 user_filespec()	563
12.55.3.4 set_defaults()	563
12.55.3.5 auto_option_save() [1/2]	563
12.55.3.6 legacy_format() [1/2]	564
12.55.3.7 lash_support() [1/2]	564
12.55.3.8 allow_mod4_mode() [1/2]	564
12.55.3.9 allow_snap_split() [1/2]	564
12.55.3.10show_midi() [1/2]	564
12.55.3.11priority() [1/2]	564
12.55.3.12stats() [1/2]	564
12.55.3.13pass_sysex() [1/2]	564
12.55.3.14with_jack_transport() [1/2]	564
12.55.3.15with_jack_master() [1/2]	564
12.55.3.16with_jack_master_cond() [1/2]	565
12.55.3.17with_jack()	565
12.55.3.18filter_by_channel() [1/2]	565
12.55.3.19manual_alsa_ports() [1/2]	565
12.55.3.20reveal_alsa_ports() [1/2]	565
12.55.3.21print_keys() [1/2]	565
12.55.3.22device_ignore() [1/2]	565
12.55.3.23device_ignore_num() [1/2]	565
12.55.3.24nteraction_method() [1/2]	565
12.55.3.25ilename() [1/2]	565
12.55.3.26ack_session_uuid() [1/2]	566

12.55.3.27last_used_dir() [1/2] 566
12.55.3.2&onfig_directory() [1/2] 566
12.55.3.29config_filename() [1/2] 566
12.55.3.30user_filename() [1/2]
12.55.3.31config_filename_alt() [1/2]
12.55.3.32user_filename_alt() [1/2]
12.55.3.33auto_option_save() [2/2]
12.55.3.34egacy_format() [2/2] 566
12.55.3.35ash_support() [2/2] 566
12.55.3.36allow_mod4_mode() [2/2]
12.55.3.37allow_snap_split() [2/2]
12.55.3.38show_midi() [2/2]
12.55.3.39priority() [2/2]
12.55.3.40stats() [2/2]
12.55.3.41pass_sysex() [2/2] 567
12.55.3.42with_jack_transport() [2/2]
12.55.3.43with_jack_master() [2/2] 567
12.55.3.44with_jack_master_cond() [2/2]
12.55.3.45 ilter_by_channel() [2/2]
12.55.3.46manual_alsa_ports() [2/2]
12.55.3.47reveal_alsa_ports() [2/2]
12.55.3.4&print_keys() [2/2]
12.55.3.49device_ignore() [2/2] 568
12.55.3.50device_ignore_num() [2/2]
12.55.3.51interaction_method() [2/2]
12.55.3.52ilename() [2/2]
12.55.3.53ack_session_uuid() [2/2]
12.55.3.54ast_used_dir() [2/2] 569
12.55.3.55config_directory() [2/2]
12.55.3.56set_config_files()

IXXXIV

12.55.3.57config_filename() [2/2]	 ′0
12.55.3.5&user_filename() [2/2]	 '0
12.55.3.59config_filename_alt() [2/2]	 ' 0
12.55.3.60user_filename_alt() [2/2]	 ' 0
12.55.3.61home_config_directory()	 ⁷ 1
12.55.4 Friends And Related Function Documentation	 ⁷ 1
12.55.4.1 optionsfile	 ⁷ 1
12.55.4.2 options	 7 1
12.55.4.3 mainwnd	 ⁷ 1
12.55.4.4 parse_command_line_options	 7 1
12.55.4.5 help_check	 '2
12.55.5 Field Documentation	 '2
12.55.5.1 m_auto_option_save	 ′2
12.55.5.2 m_legacy_format	 '2
12.55.5.3 m_lash_support	 '2
12.55.5.4 m_allow_mod4_mode	 '2
12.55.5.5 m_allow_snap_split	 '2
12.55.5.6 m_show_midi	 7 3
12.55.5.7 m_priority	 ′3
12.55.5.8 m_stats	 ′3
12.55.5.9 m_pass_sysex	 ′3
12.55.5.10m_with_jack_transport	 ′3
12.55.5.11m_with_jack_master	 7 3
12.55.5.12m_with_jack_master_cond	 ′3
12.55.5.13m_filter_by_channel	 7 3
12.55.5.14m_manual_alsa_ports	 ′3
12.55.5.15m_reveal_alsa_ports	 ′3
12.55.5.16m_print_keys	 ⁷ 4
12.55.5.17m_device_ignore	 ⁷ 4
12.55.5.18m_device_ignore_num	 7 4

12	.55.5.19m_interaction_method	574
12	.55.5.20m_filename	574
12	.55.5.21m_jack_session_uuid	574
12	.55.5.22m_last_used_dir	574
12	.55.5.23m_config_directory	574
12	.55.5.24m_config_filename	574
12	.55.5.25m_user_filename	575
12	.55.5.26m_config_filename_alt	575
12	.55.5.27m_user_filename_alt	575
12.56seq64::red	t Class Reference	575
12.56.1 Fi	eld Documentation	575
12	.56.1.1 x	575
12	.56.1.2 y	575
12	.56.1.3 height	575
12	.56.1.4 width	576
12.57seq64::gu	_drawingarea_gtk2::rect Struct Reference	576
12.57.1 Fi	eld Documentation	576
12	.57.1.1 x	576
12		
	.57.1.2 y	576
	.57.1.2 y	
12		576
12	.57.1.3 height	576 576
12 12 12.58seq64::Se	.57.1.3 height	576 576 577
12 12.58seq64::Se 12.58.1 Co	.57.1.3 height	576 576 577 578
12.58seq64::Se 12.58.1 Co	.57.1.3 height	576 576 577 578 578
12.58seq64::Se 12.58.1 Co 12.58.2 Me	.57.1.3 height	576 576 577 578 578 578
12.58seq64::Se 12.58.1 Co 12.58.2 Mc	.57.1.3 height .57.1.4 width	576 576 577 578 578 578
12.58seq64::Se 12.58.1 Co 12.58.2 Mc	.57.1.3 height	576 576 577 578 578 578 578
12.58seq64::Se 12.58.1 Co 12.58.2 Mo 12.58.2 Mo	.57.1.3 height .57.1.4 width	576 576 577 578 578 578 578 579

IXXXVI

12.58.3 Friends And Related Function Documentation	580
12.58.3.1 perfroll	580
12.58.4 Field Documentation	580
12.58.4.1 m_effective_tick	580
12.59seq64::Seq24SeqEventInput Struct Reference	580
12.59.1 Constructor & Destructor Documentation	581
12.59.1.1 Seq24SeqEventInput()	581
12.59.2 Member Function Documentation	581
12.59.2.1 set_adding()	581
12.59.2.2 on_button_press_event()	581
12.59.2.3 on_button_release_event()	582
12.59.2.4 on_motion_notify_event()	582
12.59.3 Field Documentation	582
12.59.3.1 m_adding	582
12.60seq64::seqdata Class Reference	582
12.60.1 Constructor & Destructor Documentation	585
12.60.1 Constructor & Destructor Documentation	
	585
12.60.1.1 seqdata()	585 586
12.60.1.1 seqdata()	585 586 586
12.60.1.1 seqdata()	585 586 586 586
12.60.1.1 seqdata()	585 586 586 586
12.60.1.1 seqdata()	585 586 586 586 586
12.60.1.1 seqdata()	585 586 586 586 586 586
12.60.1.1 seqdata()	585 586 586 586 586 586 587
12.60.1.1 seqdata()	585 586 586 586 586 586 587
12.60.1.1 seqdata()	585 586 586 586 586 586 587 587
12.60.1.1 seqdata()	585 586 586 586 586 587 587 587
12.60.1.1 seqdata()	585 586 586 586 586 587 587 587
12.60.1.1 seqdata() 12.60.1.2 ~seqdata() 12.60.2 Member Function Documentation 12.60.2.1 reset() 12.60.2.2 redraw() 12.60.2.3 set_zoom() 12.60.2.4 set_data_type() 12.60.2.5 idle_redraw() 12.60.2.6 update_sizes() 12.60.2.7 update_pixmap() 12.60.2.8 draw_line_on_window() 12.60.2.9 xy_to_rect()	585 586 586 586 586 587 587 587 587

12.60.2.12convert_x()
12.60.2.13render_number()
12.60.2.14draw_events_on_pixmap()
12.60.2.15draw_pixmap_on_window()
12.60.2.16on_realize()
12.60.2.17on_expose_event()
12.60.2.18on_button_press_event()
12.60.2.19on_button_release_event()
12.60.2.20on_motion_notify_event()
12.60.2.21on_leave_notify_event()
12.60.2.22on_scroll_event()
12.60.2.23on_size_allocate()
12.60.3 Friends And Related Function Documentation
12.60.3.1 Ifownd
12.60.3.2 seqevent
12.60.3.3 seqroll
12.60.4 Field Documentation
12.60.4.1 m_seq
12.60.4.2 m_zoom
12.60.4.3 m_scroll_offset_ticks
12.60.4.4 m_scroll_offset_x
12.60.4.5 m_number_w
12.60.4.6 m_number_h
12.60.4.7 m_number_offset_y
12.60.4.8 m_status
12.60.4.9 m_cc
12.60.4.10m_numbers
12.60.4.11m_old
12.60.4.12m_drag_handle
12.60.4.13m_dragging

Ixxxviii CONTENTS

12.61 seq64::seqedit Class Reference
12.61.1 Detailed Description
12.61.2 Constructor & Destructor Documentation
12.61.2.1 seqedit()
12.61.2.2 ~seqedit()
12.61.3 Member Function Documentation
12.61.3.1 set_zoom()
12.61.3.2 set_snap()
12.61.3.3 set_note_length()
12.61.3.4 set_beats_per_bar()
12.61.3.5 set_beat_width()
12.61.3.6 set_transpose_image()
12.61.3.7 set_rec_vol()
12.61.3.8 horizontal_adjust()
12.61.3.9 vertical_adjust()
12.61.3.10horizontal_set()
12.61.3.11vertical_set()
12.61.3.12set_measures()
12.61.3.13apply_length()
12.61.3.14get_measures()
12.61.3.15set_midi_channel()
12.61.3.16set_midi_bus()
12.61.3.17set_scale()
12.61.3.18set_chord()
12.61.3.19set_key()
12.61.3.20set_background_sequence()
12.61.3.21transpose_change_callback()
12.61.3.22name_change_callback()
12.61.3.23play_change_callback()
12.61.3.24record_change_callback()

12.61.3.25q_rec_change_callback()	606
12.61.3.26thru_change_callback()	606
12.61.3.27undo_callback()	607
12.61.3.28 edo_callback()	607
12.61.3.29set_data_type()	607
12.61.3.30update_all_windows()	607
12.61.3.31fill_top_bar()	607
12.61.3.32create_menus()	607
12.61.3.33popup_menu()	608
12.61.3.34popup_event_menu()	608
12.61.3.35popup_midibus_menu()	608
12.61.3.3@popup_sequence_menu()	608
12.61.3.37popup_tool_menu()	609
12.61.3.3&popup_midich_menu()	609
12.61.3.39create_menu_image()	609
12.61.3.40timeout()	609
12.61.3.41do_action()	609
12.61.3.42mouse_action()	609
12.61.3.43start_playing()	609
12.61.3.44stop_playing()	609
12.61.3.45change_focus()	609
12.61.3.46handle_close()	610
12.61.3.47on_realize()	610
12.61.3.4&n_set_focus()	610
12.61.3.49on_focus_in_event()	610
12.61.3.50on_focus_out_event()	610
12.61.3.51on_delete_event()	610
12.61.3.52on_scroll_event()	611
12.61.3.53on_key_press_event()	611
12.61.4 Field Documentation	612

xc CONTENTS

12.61.4.1 seqmenu
12.61.4.2 m_initial_snap
12.61.4.3 m_initial_note_length
12.61.4.4 m_initial_chord
12.61.4.5 m_initial_zoom
12.61.4.6 m_zoom
12.61.4.7 m_snap
12.61.4.8 m_note_length
12.61.4.9 m_scale
12.61.4.10m_chord
12.61.4.11m_key
12.61.4.12m_bgsequence
12.61.4.13m_measures
12.61.4.14m_ppqn
12.61.4.15m_pp_whole
12.61.4.16m_pp_eighth
12.61.4.17m_pp_sixteenth
12.61.4.18m_seq
12.61.4.19m_menubar
12.61.4.20m_menu_tools
12.61.4.21m_menu_zoom
12.61.4.22m_menu_snap
12.61.4.23m_menu_note_length
12.61.4.24m_menu_length
12.61.4.25m_toggle_transpose
12.61.4.26m_image_transpose
12.61.4.27m_menu_midich
12.61.4.28m_menu_midibus
12.61.4.29m_menu_data
12.61.4.30m_menu_key

CONTENTS xci

12.61.4.31m_menu_scale
12.61.4.32m_menu_chords
12.61.4.33m_menu_sequences
12.61.4.34m_menu_bpm
12.61.4.35m_menu_bw
12.61.4.36m_button_lfo
12.61.4.37m_lfo_wnd
12.61.4.38m_menu_rec_vol
12.61.4.39m_vadjust
12.61.4.40m_hadjust
12.61.4.41m_vscroll_new
12.61.4.42m_hscroll_new
12.61.4.43m_seqkeys_wid
12.61.4.44m_seqtime_wid
12.61.4.45m_seqdata_wid
12.61.4.46m_seqevent_wid
12.61.4.47m_seqroll_wid
12.61.4.48m_table
12.61.4.49m_vbox
12.61.4.50m_hbox
12.61.4.51m_hbox2
12.61.4.52m_button_undo
12.61.4.53m_button_redo
12.61.4.54m_button_quantize
12.61.4.55m_button_tools
12.61.4.56m_button_sequence
12.61.4.57m_entry_sequence
12.61.4.58m_button_bus
12.61.4.59m_entry_bus
12.61.4.60m_button_channel

xcii CONTENTS

12.61.4.61m_entry_channel
12.61.4.62m_button_snap
12.61.4.63m_entry_snap
12.61.4.64m_button_note_length
12.61.4.65m_entry_note_length
12.61.4.60m_button_zoom
12.61.4.67m_entry_zoom
12.61.4.68m_button_length
12.61.4.69m_entry_length
12.61.4.70m_button_key
12.61.4.71m_entry_key
12.61.4.72m_button_scale
12.61.4.73m_entry_scale
12.61.4.74m_button_chord
12.61.4.75m_entry_chord
12.61.4.76m_tooltips
12.61.4.77m_button_data
12.61.4.78m_entry_data
12.61.4.79m_button_bpm
12.61.4.80m_entry_bpm
12.61.4.81m_button_bw
12.61.4.82m_entry_bw
12.61.4.83m_button_rec_vol
12.61.4.84m_toggle_play
12.61.4.85m_toggle_record
12.61.4.86m_toggle_q_rec
12.61.4.87m_toggle_thru
12.61.4.88m_entry_name
12.61.4.89m_editing_status
12.61.4.90m_editing_cc

CONTENTS xciii

xciv CONTENTS

12.62.2.25on_button_press_event()	30
12.62.2.26on_button_release_event()	31
12.62.2.27on_motion_notify_event()	31
12.62.2.28on_focus_in_event()	32
12.62.2.29on_focus_out_event()	32
12.62.2.30on_key_press_event()	32
12.62.2.31on_size_allocate()	32
12.62.3 Friends And Related Function Documentation	33
12.62.3.1 FruitySeqEventInput	33
12.62.3.2 Seq24SeqEventInput	33
12.62.4 Field Documentation	33
12.62.4.1 m_fruity_interaction	33
12.62.4.2 m_seq24_interaction	33
12.62.4.3 m_seq	33
12.62.4.4 m_zoom	33
12.62.4.5 m_snap	33
12.62.4.6 m_ppqn	34
12.62.4.7 m_old	34
12.62.4.8 m_selected	34
12.62.4.9 m_scroll_offset_ticks	34
12.62.4.10m_scroll_offset_x	34
12.62.4.11m_seqdata_wid	34
12.62.4.12m_selecting	34
12.62.4.13m_moving_init	34
12.62.4.14m_moving	34
12.62.4.15m_growing	35
12.62.4.16m_painting	35
12.62.4.17m_paste	35
12.62.4.18m_move_snap_offset_x	35
12.62.4.19m_status	35

CONTENTS xcv

12.62.4.20m_cc	35
12.63seq64::seqkeys Class Reference	36
12.63.1 Detailed Description	38
12.63.2 Constructor & Destructor Documentation	38
12.63.2.1 seqkeys()	38
12.63.2.2 ~seqkeys()	39
12.63.3 Member Function Documentation	39
12.63.3.1 set_scale()	39
12.63.3.2 set_key()	39
12.63.3.3 set_hint_key()	39
12.63.3.4 set_hint_state()	39
12.63.3.5 force_draw()	40
12.63.3.6 set_listen_button_press()	40
12.63.3.7 set_listen_button_release()	40
12.63.3.8 set_listen_motion_notify()	40
12.63.3.9 draw_area()	40
12.63.3.10update_pixmap()	40
12.63.3.11convert_y()	40
12.63.3.12draw_key()	41
12.63.3.13change_vert()	41
12.63.3.14update_sizes()	41
12.63.3.15reset()	41
12.63.3.16s_black_key()	41
12.63.3.17on_realize()	42
12.63.3.18on_expose_event()	42
12.63.3.19on_button_press_event()	42
12.63.3.2@n_button_release_event()	42
12.63.3.21on_motion_notify_event()	43
12.63.3.22on_enter_notify_event()	43
12.63.3.23on_leave_notify_event()	43

xcvi CONTENTS

12.63.3.24on_scroll_event()	43
12.63.3.25on_size_allocate()	44
12.63.4 Friends And Related Function Documentation	44
12.63.4.1 seqroll	44
12.63.4.2 FruitySeqRollInput	44
12.63.5 Field Documentation	44
12.63.5.1 m_seq	44
12.63.5.2 m_scroll_offset_key	44
12.63.5.3 m_scroll_offset_y	44
12.63.5.4 m_hint_state	45
12.63.5.5 m_hint_key	45
12.63.5.6 m_keying	45
12.63.5.7 m_keying_note	45
12.63.5.8 m_scale	45
12.63.5.9 m_key	45
12.63.5.10m_show_octave_letters	45
12.64seq64::seqmenu Class Reference	46
12.64.1 Detailed Description	49
12.64.2 Constructor & Destructor Documentation	49
12.64.2.1 seqmenu()	49
12.64.2.2 ~seqmenu()	49
12.64.3 Member Function Documentation	49
12.64.3.1 current_seq() [1/2]	49
12.64.3.2 is_modified() [1/2]	49
12.64.3.3 current_seq() [2/2]	49
12.64.3.4 set_edit_sequence()	50
12.64.3.5 unset_edit_sequence()	50
12.64.3.6 is_edit_sequence()	50
12.64.3.7 is_modified() [2/2]	50
12.64.3.8 get_current_sequence()	50

CONTENTS xcvii

	12.64.3.9 get_sequence()	650
	12.64.3.10s_current_seq_active()	650
	12.64.3.11is_current_seq_in_edit()	650
	12.64.3.12new_current_sequence()	650
	12.64.3.13new_sequence()	651
	12.64.3.14delete_current_sequence()	651
	12.64.3.15toggle_current_sequence()	651
	12.64.3.1@popup_menu()	651
	12.64.3.17seq_edit()	651
	12.64.3.18seq_event_edit()	651
	12.64.3.19seq_set_and_edit()	651
	12.64.3.20seq_set_and_eventedit()	652
	12.64.3.21redraw()	652
	12.64.3.22seq_new()	652
	12.64.3.23seq_copy()	652
	12.64.3.24seq_cut()	652
	12.64.3.25seq_paste()	653
	12.64.3.26seq_clear_perf()	653
	12.64.3.27set_bus_and_midi_channel()	653
	12.64.3.28set_transposable()	653
	12.64.3.29mute_all_tracks()	653
	12.64.3.30unmute_all_tracks()	653
	12.64.3.31toggle_all_tracks()	653
	12.64.3.32on_realize()	654
12.64.4	4 Friends And Related Function Documentation	654
	12.64.4.1 mainwnd	654
12.64.5	5 Field Documentation	654
	12.64.5.1 m_menu	654
	12.64.5.2 m_mainperf	654
	12.64.5.3 m_clipboard	654

xcviii CONTENTS

12.64.5.4 m_seqedit	4
12.64.5.5 m_eventedit	4
12.64.5.6 m_current_seq	4
12.64.5.7 m_modified	4
12.65seq64::seqroll Class Reference	5
12.65.1 Constructor & Destructor Documentation	0
12.65.1.1 seqroll()	0
12.65.1.2 ~seqroll()	1
12.65.2 Member Function Documentation	1
12.65.2.1 set_snap()	1
12.65.2.2 set_zoom()	1
12.65.2.3 set_note_length()	1
12.65.2.4 note_off_length()	2
12.65.2.5 add_note()	2
12.65.2.6 add_chord()	2
12.65.2.7 set_key()	2
12.65.2.8 set_scale()	3
12.65.2.9 set_chord()	3
12.65.2.10set_data_type()	3
12.65.2.11set_background_sequence()	3
12.65.2.12update_pixmap()	3
12.65.2.13update_sizes()	4
12.65.2.14update_background()	4
12.65.2.15draw_background_on_pixmap()	4
12.65.2.16draw_events_on_pixmap()	4
12.65.2.17draw_selection_on_window()	4
12.65.2.18draw_progress_on_window()	5
12.65.2.19reset()	5
12.65.2.20update_and_draw()	5
12.65.2.21redraw()	5

CONTENTS xcix

12.65.2.22redraw_events()
12.65.2.23start_paste()
12.65.2.24complete_paste() [1/2]
12.65.2.25complete_paste() [2/2]
12.65.2.26follow_progress()
12.65.2.27force_draw()
12.65.2.28horizontal_adjust()
12.65.2.29vertical_adjust()
12.65.2.30snap_y()
12.65.2.31snap_x()
12.65.2.32convert_xy()
12.65.2.33convert_tn()
12.65.2.34xy_to_rect()
12.65.2.35convert_tn_box_to_rect()
12.65.2.3@convert_sel_box_to_rect()
12.65.2.37get_selected_box()
12.65.2.3&draw_events_on()
12.65.2.39dle_redraw()
12.65.2.40dle_progress()
12.65.2.41change_horz()
12.65.2.42change_vert()
12.65.2.43move_selection_box()
12.65.2.44move_selected_notes()
12.65.2.45grow_selected_notes()
12.65.2.46set_adding()
12.65.2.47update_mouse_pointer()
12.65.2.48button_press_initial()
12.65.2.49align_selection()
12.65.2.50button_press()
12.65.2.51button_release()

CONTENTS CONTENTS

12.65.2.52motion_notify()	 674
12.65.2.53clear_selected()	 674
12.65.2.54clear_old()	 674
12.65.2.55clear_flags()	 674
12.65.2.56scroll_offset_x()	 674
12.65.2.57scroll_offset_y()	 674
12.65.2.58set_current_offset_x_y()	 675
12.65.2.59adding()	 675
12.65.2.60selecting()	 675
12.65.2.61growing()	 675
12.65.2.62normal_action()	 676
12.65.2.63select_action()	 676
12.65.2.64drop_action()	 676
12.65.2.65moving()	 676
12.65.2.66on_realize()	 676
12.65.2.67on_expose_event()	 676
12.65.2.68on_button_press_event()	 677
12.65.2.69on_button_release_event()	 677
12.65.2.70on_motion_notify_event()	 677
12.65.2.71on_focus_in_event()	 678
12.65.2.72on_focus_out_event()	 678
12.65.2.73on_key_press_event()	 678
12.65.2.74on_scroll_event()	 679
12.65.2.75on_size_allocate()	 679
12.65.2.76on_leave_notify_event()	 679
12.65.2.77on_enter_notify_event()	 679
12.65.3 Friends And Related Function Documentation	 680
12.65.3.1 FruitySeqRollInput	 680
12.65.4 Field Documentation	 680
12.65.4.1 m_horizontal_adjust	 680

12.65.4.2 m_vertical_adjust
12.65.4.3 m_old
12.65.4.4 m_selected
12.65.4.5 m_seq
12.65.4.6 m_seqkeys_wid
12.65.4.7 m_fruity_interaction
12.65.4.8 m_pos
12.65.4.9 m_zoom
12.65.4.10m_snap
12.65.4.11m_ppqn
12.65.4.12m_note_length
12.65.4.13m_scale
12.65.4.14m_chord
12.65.4.15m_key
12.65.4.16m_adding
12.65.4.17m_selecting
12.65.4.18m_moving
12.65.4.19m_moving_init
12.65.4.20m_growing
12.65.4.21m_painting
12.65.4.22m_paste
12.65.4.23m_is_drag_pasting
12.65.4.24m_is_drag_pasting_start
12.65.4.25m_justselected_one
12.65.4.26m_move_delta_x
12.65.4.27m_move_delta_y
12.65.4.28m_move_snap_offset_x
12.65.4.29m_progress_x
12.65.4.30m_scroll_offset_ticks
12.65.4.31m_scroll_offset_key

cii CONTENTS

12.65.4.32m_scroll_offset_x	683
12.65.4.33m_scroll_offset_y	683
12.65.4.34m_transport_follow	683
12.65.4.35m_trans_button_press	683
12.65.4.36m_background_sequence	684
12.65.4.37m_drawing_background_seq	684
12.65.4.38m_status	684
12.65.4.39m_cc	684
12.66seq64::seqtime Class Reference	684
12.66.1 Constructor & Destructor Documentation	686
12.66.1.1 seqtime()	686
12.66.1.2 ~seqtime()	687
12.66.2 Member Function Documentation	687
12.66.2.1 reset()	687
12.66.2.2 redraw()	687
12.66.2.3 set_zoom()	687
12.66.2.4 draw_pixmap_on_window()	687
12.66.2.5 draw_progress_on_window()	687
12.66.2.6 update_pixmap()	687
12.66.2.7 change_horz()	688
12.66.2.8 update_sizes()	688
12.66.2.9 idle_progress()	688
12.66.2.1@n_realize()	688
12.66.2.11on_expose_event()	688
12.66.2.12on_size_allocate()	688
12.66.2.13on_button_press_event()	689
12.66.2.14on_button_release_event()	689
12.66.3 Field Documentation	689
12.66.3.1 m_seq	689
12.66.3.2 m_scroll_offset_ticks	689

12.66.3.3 m_scroll_offset_x	689
12.66.3.4 m_zoom	689
12.66.3.5 m_ppqn	689
12.67seq64::sequence Class Reference	689
12.67.1 Detailed Description	700
12.67.2 Member Typedef Documentation	700
12.67.2.1 EventStack	700
12.67.3 Member Enumeration Documentation	700
12.67.3.1 select_action_e	700
12.67.4 Constructor & Destructor Documentation	701
12.67.4.1 sequence()	701
12.67.4.2 ~sequence()	701
12.67.5 Member Function Documentation	701
12.67.5.1 operator=()	701
12.67.5.2 partial_assign()	701
12.67.5.3 events() [1/2]	701
12.67.5.4 events() [2/2]	701
12.67.5.5 any_selected_notes()	702
12.67.5.6 triggerlist() [1/2]	702
12.67.5.7 triggerlist() [2/2]	702
12.67.5.8 get_trigger_count()	702
12.67.5.9 set_trigger_paste_tick()	702
12.67.5.10get_trigger_paste_tick()	702
12.67.5.11number() [1/2]	702
12.67.5.12number() [2/2]	702
12.67.5.13modify()	702
12.67.5.14event_count()	703
12.67.5.15set_hold_undo()	703
12.67.5.1&get_hold_undo()	703
12.67.5.17set_have_undo()	703

12.67.5.18have_undo()
12.67.5.19set_have_redo()
12.67.5.20have_redo()
12.67.5.21push_undo()
12.67.5.22pop_undo()
12.67.5.23pop_redo()
12.67.5.24push_trigger_undo()
12.67.5.25pop_trigger_undo()
12.67.5.26pop_trigger_redo()
12.67.5.27set_name() [1/2]
12.67.5.28set_name() [2/2]
12.67.5.29set_measures()
12.67.5.30get_measures()
12.67.5.31get_ppqn()
12.67.5.32set_beats_per_bar()
12.67.5.33get_beats_per_bar()
12.67.5.34set_beat_width()
12.67.5.35get_beat_width()
12.67.5.36measures_to_ticks()
12.67.5.37clocks_per_metronome() [1/2]
12.67.5.3&locks_per_metronome() [2/2]
12.67.5.39set_32nds_per_quarter()
12.67.5.40get_32nds_per_quarter()
12.67.5.41us_per_quarter_note() [1/2]
12.67.5.42us_per_quarter_note() [2/2]
12.67.5.43set_rec_vol()
12.67.5.44set_song_mute()
12.67.5.45toggle_song_mute()
12.67.5.46get_song_mute()
12.67.5.47apply_song_transpose()

12.67.5.48set_transposable()
12.67.5.49get_transposable()
12.67.5.50get_name()
12.67.5.51name()
12.67.5.52set_editing()
12.67.5.53get_editing()
12.67.5.54set_raise()
12.67.5.55get_raise()
12.67.5.56set_length()
12.67.5.57get_length()
12.67.5.5&get_last_tick()
12.67.5.59set_last_tick()
12.67.5.60mod_last_tick()
12.67.5.61set_playing()
12.67.5.62get_playing()
12.67.5.63toggle_playing()
12.67.5.64toggle_queued()
12.67.5.65off_queued()
12.67.5.66on_queued()
12.67.5.67get_queued()
12.67.5.68get_queued_tick()
12.67.5.69check_queued_tick()
12.67.5.70set_recording()
12.67.5.71get_recording()
12.67.5.72set_snap_tick()
12.67.5.73set_quantized_rec()
12.67.5.74get_quantized_rec()
12.67.5.75set_thru()
12.67.5.76get_thru()
12.67.5.77s_dirty_main()

12.67.5.78s_dirty_edit()
12.67.5.79s_dirty_perf()
12.67.5.8ûs_dirty_names()
12.67.5.81set_dirty_mp()
12.67.5.82set_dirty()
12.67.5.83get_midi_channel()
12.67.5.84s_smf_0()
12.67.5.85set_midi_channel()
12.67.5.8@print()
12.67.5.87print_triggers()
12.67.5.8&play()
12.67.5.89play_queue()
12.67.5.90add_event() [1/2]
12.67.5.91add_trigger()
12.67.5.92split_trigger()
12.67.5.93grow_trigger()
12.67.5.94del_trigger()
12.67.5.95get_trigger_state()
12.67.5.96select_trigger()
12.67.5.97get_triggers()
12.67.5.9&unselect_triggers()
12.67.5.99ntersect_triggers()
12.67.5.1000tersect_notes()
12.67.5.10/mtersect_events()
12.67.5.1022el_selected_trigger()
12.67.5.103ut_selected_trigger()
12.67.5.10s/ppy_selected_trigger()
12.67.5.10p5aste_trigger()
12.67.5.10@nove_selected_triggers_to()
12.67.5.10 s elected_trigger_start()

CONTENTS cvii

12.67.5.10 <u>Relected_trigger_end()</u>
12.67.5.10get_max_trigger()
12.67.5.11m0ove_triggers()
12.67.5.11dopy_triggers()
12.67.5.11@lear_triggers()
12.67.5.11@et_trigger_offset()
12.67.5.11stet_midi_bus()
12.67.5.11 g et_midi_bus()
12.67.5.11 s et_master_midi_bus()
12.67.5.11 s elect_note_events()
12.67.5.11&elect_events() [1/3]
12.67.5.119elect_events() [2/3]
12.67.5.12@elect_events() [3/3]
12.67.5.12stelect_event_handle()
12.67.5.12% elect_linked()
12.67.5.123elect_even_or_odd_notes()
12.67.5.12stelect_all_notes()
12.67.5.125et_num_selected_notes()
12.67.5.126et_num_selected_events()
12.67.5.125elect_all()
12.67.5.128ppy_selected()
12.67.5.129ut_selected()
12.67.5.13paste_selected()
12.67.5.13get_selected_box()
12.67.5.13get_clipboard_box()
12.67.5.13adjust_timestamp()
12.67.5.134im_timestamp()
12.67.5.13 5 jp_timestamp()
12.67.5.13% ove_selected_notes()
12.67.5.13a7dd_note()

cviii CONTENTS

12.67.5.13a2dd_chord()
12.67.5.13add_event() [2/2]
12.67.5.14stream_event()
12.67.5.14dhange_event_data_range()
12.67.5.14@hange_event_data_lfo()
12.67.5.148crement_selected()
12.67.5.14decrement_selected()
12.67.5.14@frow_selected()
12.67.5.14stretch_selected()
12.67.5.14remove_marked()
12.67.5.14mark_selected()
12.67.5.14@move_selected()
12.67.5.15@npaint_all()
12.67.5.15t/Inselect()
12.67.5.15\(\text{2erify_and_link} \)
12.67.5.158nk_new()
12.67.5.15zero_markers()
12.67.5.15@day_note_on()
12.67.5.15@day_note_off()
12.67.5.150ff_playing_notes()
12.67.5.15@ause()
12.67.5.15@set()
12.67.5.16@set_draw_marker()
12.67.5.16/eset_draw_trigger_marker()
12.67.5.16@let_next_note_event()
12.67.5.16@et_minmax_note_events()
12.67.5.16glet_next_event() [1/2]
12.67.5.165jet_next_event() [2/2]
12.67.5.16@jet_next_trigger()
12.67.5.16quantize_events()

12.67.5.16 ausn_quantize()	/41
12.67.5.16@anspose_notes()	741
12.67.5.1 7\$ hift_notes()	741
12.67.5.17/hultiply_pattern()	741
12.67.5.17/20usical_key() [1/2]	741
12.67.5.1778husical_key() [2/2]	742
12.67.5.17\(\alpha\)usical_scale() [1/2]	742
12.67.5.17/msusical_scale() [2/2]	742
12.67.5.176ackground_sequence() [1/2]	742
12.67.5.1767ackground_sequence() [2/2]	742
12.67.5.17 s how_events()	742
12.67.5.17@opy_events()	742
12.67.5.180ote_off_margin()	743
12.67.5.18dvent_in_range()	743
12.67.5.182et_parent()	743
12.67.5.18p3ut_event_on_bus()	743
12.67.5.184et_trigger_offset()	744
12.67.5.18 Edjust_trigger_offsets_to_length()	744
12.67.5.18 26 djust_offset()	744
12.67.5.187emove() [1/2]	744
12.67.5.18@move() [2/2]	745
12.67.5.189emove_all()	745
12.67.5.19@channel_match()	745
12.67.6 Friends And Related Function Documentation	745
12.67.6.1 perform	745
12.67.6.2 triggers	745
12.67.7 Field Documentation	746
12.67.7.1 m_events_clipboard	746
12.67.7.2 m_parent	746
12.67.7.3 m_events	746
12.07.7.3 III_events	740

12.67.7.4 m_triggers
12.67.7.5 m_events_undo_hold
12.67.7.6 m_have_undo
12.67.7.7 m_have_redo
12.67.7.8 m_events_undo
12.67.7.9 m_events_redo
12.67.7.10m_iterator_draw
12.67.7.11m_channel_match
12.67.7.12m_midi_channel
12.67.7.13m_bus
12.67.7.14m_song_mute
12.67.7.15m_transposable
12.67.7.16m_notes_on
12.67.7.17m_masterbus
12.67.7.18m_playing_notes
12.67.7.19m_was_playing
12.67.7.20m_playing
12.67.7.21m_recording
12.67.7.22m_quantized_rec
12.67.7.23m_thru
12.67.7.24m_queued
12.67.7.25m_dirty_main
12.67.7.26m_dirty_edit
12.67.7.27m_dirty_perf
12.67.7.28m_dirty_names
12.67.7.29m_editing
12.67.7.30m_raise
12.67.7.31m_name
12.67.7.32m_last_tick
12.67.7.33m_queued_tick

12.67.7.34m_trigger_offset
12.67.7.35m_maxbeats
12.67.7.36m_ppqn
12.67.7.37m_seq_number
12.67.7.38m_length
12.67.7.39m_snap_tick
12.67.7.40m_time_beats_per_measure
12.67.7.41m_time_beat_width
12.67.7.42m_clocks_per_metronome
12.67.7.43m_32nds_per_quarter
12.67.7.44m_us_per_quarter_note
12.67.7.45m_rec_vol
12.67.7.46m_note_on_velocity
12.67.7.47m_note_off_velocity
12.67.7.48m_musical_key
12.67.7.49m_musical_scale
12.67.7.50m_background_sequence
12.67.7.51m_mutex
12.67.7.52m_note_off_margin
12.68seq64::trigger Class Reference
12.68.1 Detailed Description
12.68.2 Constructor & Destructor Documentation
12.68.2.1 trigger()
12.68.3 Member Function Documentation
12.68.3.1 operator<()
12.68.3.2 length()
12.68.3.3 tick_start() [1/2]
12.68.3.4 tick_start() [2/2]
12.68.3.5 increment_tick_start()
12.68.3.6 decrement_tick_start()

12.68.3.7 tick_end() [1/2]	 754
12.68.3.8 tick_end() [2/2]	 754
12.68.3.9 increment_tick_end()	 754
12.68.3.10decrement_tick_end()	 755
12.68.3.11offset() [1/2]	 755
12.68.3.12offset() [2/2]	 755
12.68.3.13ncrement_offset()	 755
12.68.3.14decrement_offset()	 755
12.68.3.15selected() [1/2]	 755
12.68.3.16selected() [2/2]	 755
12.68.4 Field Documentation	 755
12.68.4.1 m_tick_start	 755
12.68.4.2 m_tick_end	 755
12.68.4.3 m_offset	 756
12.68.4.4 m_selected	 756
12.69seq64::triggers Class Reference	 756
12.69.1 Member Typedef Documentation	 758
12.69.1.1 List	 758
12.69.1.2 Stack	 759
12.69.2 Member Enumeration Documentation	 759
12.69.2.1 grow_edit_t	 759
12.69.3 Constructor & Destructor Documentation	 760
12.69.3.1 triggers()	 760
12.69.3.2 ~triggers()	 760
12.69.4 Member Function Documentation	 760
12.69.4.1 operator=()	 760
12.69.4.2 set_ppqn()	 760
12.69.4.3 set_length()	 761
12.69.4.4 triggerlist() [1/2]	 761
12.69.4.5 triggerlist() [2/2]	 761

CONTENTS cxiii

12.69.4.6 push_undo()
12.69.4.7 pop_undo()
12.69.4.8 pop_redo()
12.69.4.9 print()
12.69.4.10play()
12.69.4.11add()
12.69.4.12adjust_offsets_to_length()
12.69.4.13split() [1/2]
12.69.4.14grow()
12.69.4.15remove()
12.69.4.16get_state()
12.69.4.17select()
12.69.4.1&unselect()
12.69.4.19ntersect()
12.69.4.20remove_selected()
12.69.4.21copy_selected()
12.69.4.22paste()
12.69.4.23move_selected()
12.69.4.24get_selected_start()
12.69.4.25get_selected_end()
12.69.4.26get_maximum()
12.69.4.27move()
12.69.4.2©()
12.69.4.29clear()
12.69.4.30next()
12.69.4.31next_trigger()
12.69.4.32reset_draw_trigger_marker()
12.69.4.33set_trigger_paste_tick()
12.69.4.34get_trigger_paste_tick()
12.69.4.35adjust_offset()

	12.69.4.36split() [2/2]	770
12.69.5 l	Friends And Related Function Documentation	770
	12.69.5.1 midi_container	770
	12.69.5.2 midifile	770
	12.69.5.3 sequence	771
-	12.69.5.4 Seq24PerfInput	771
	12.69.5.5 FruityPerfInput	771
12.69.6 I	Field Documentation	771
-	12.69.6.1 m_parent	771
-	12.69.6.2 m_triggers	771
-	12.69.6.3 m_clipboard	771
-	12.69.6.4 m_undo_stack	771
-	12.69.6.5 m_redo_stack	771
-	12.69.6.6 m_iterator_play_trigger	771
-	12.69.6.7 m_iterator_draw_trigger	771
-	12.69.6.8 m_trigger_copied	772
-	12.69.6.9 m_paste_tick	772
-	12.69.6.10m_ppqn	772
-	12.69.6.11m_length	772
12.70seq64::u	ser_instrument Class Reference	772
12.70.1 I	Detailed Description	773
12.70.2	Constructor & Destructor Documentation	773
	12.70.2.1 user_instrument() [1/2]	773
	12.70.2.2 user_instrument() [2/2]	773
12.70.3	Member Function Documentation	773
	12.70.3.1 operator=()	774
	12.70.3.2 is_valid()	774
-	12.70.3.3 set_defaults()	774
	12.70.3.4 name()	774
-	12.70.3.5 controller_count()	774

12.70.3.6 controller_max()	774
12.70.3.7 controller_name()	774
12.70.3.8 controller_active()	775
12.70.3.9 set_controller()	775
12.70.3.10set_name()	775
12.70.3.11copy_definitions()	776
12.70.4 Field Documentation	776
12.70.4.1 m_is_valid	776
12.70.4.2 m_controller_count	776
12.70.4.3 m_instrument_def	776
12.71seq64::user_instrument_t Struct Reference	776
12.71.1 Field Documentation	777
12.71.1.1 instrument	777
12.71.1.2 controllers	777
12.71.1.3 controllers_active	777
12.72seq64::user_midi_bus Class Reference	777
12.72.1 Detailed Description	778
12.72.2 Constructor & Destructor Documentation	778
12.72.2.1 user_midi_bus() [1/2]	778
12.72.2.2 user_midi_bus() [2/2]	778
12.72.3 Member Function Documentation	778
12.72.3.1 operator=()	779
12.72.3.2 is_valid()	779
12.72.3.3 set_defaults()	779
12.72.3.4 name()	779
12.72.3.5 channel_count()	779
12.72.3.6 channel_max()	779
12.72.3.7 instrument()	779
12.72.3.8 set_instrument()	780
12.72.3.9 set_name()	780

12.72.3.10copy_definitions()	80
12.72.4 Field Documentation	80
12.72.4.1 m_is_valid	80
12.72.4.2 m_channel_count	80
12.72.4.3 m_midi_bus_def	81
12.73seq64::user_midi_bus_t Struct Reference	81
12.73.1 Field Documentation	81
12.73.1.1 alias	81
12.73.1.2 instrument	81
12.74seq64::user_settings Class Reference	81
12.74.1 Detailed Description	89
12.74.2 Member Typedef Documentation	89
12.74.2.1 Busses	89
12.74.2.2 BussIterator	89
12.74.2.3 BussConstIterator	89
12.74.2.4 Instruments	89
12.74.2.5 InstrumentIterator	89
12.74.2.6 InstrumentConstIterator	89
12.74.3 Member Enumeration Documentation	89
12.74.3.1 mainwid_grid_style_t	89
12.74.4 Constructor & Destructor Documentation	90
12.74.4.1 user_settings() [1/2]	90
12.74.4.2 user_settings() [2/2]	90
12.74.5 Member Function Documentation	90
12.74.5.1 operator=()	90
12.74.5.2 set_defaults()	90
12.74.5.3 normalize()	90
12.74.5.4 add_bus()	90
12.74.5.5 add_instrument()	91
12.74.5.6 bus()	91

CONTENTS cxvii

12.74.5.7 instrument()
12.74.5.8 bus_count()
12.74.5.9 set_bus_instrument()
12.74.5.10bus_instrument()
12.74.5.11bus_name()
12.74.5.12instrument_count()
12.74.5.13set_instrument_controllers()
12.74.5.14nstrument_name() [1/2]
12.74.5.15nstrument_name() [2/2]
12.74.5.16nstrument_controller_active()
12.74.5.17controller_active()
12.74.5.18instrument_controller_name()
12.74.5.19controller_name()
12.74.5.20grid_style() [1/2]
12.74.5.21grid_is_normal()
12.74.5.22grid_is_white()
12.74.5.23grid_is_black()
12.74.5.24grid_brackets() [1/2]
12.74.5.25mainwnd_rows() [1/2]
12.74.5.26mainwnd_cols() [1/2]
12.74.5.27seqs_in_set()
12.74.5.28gmute_tracks()
12.74.5.29max_sets() [1/2]
12.74.5.30max_sequence()
12.74.5.31text_x() [1/2]
12.74.5.32ext_y() [1/2]
12.74.5.33seqchars_x() [1/2]
12.74.5.34seqchars_y() [1/2]
12.74.5.35seqarea_x() [1/2]
12.74.5.36seqarea_y() [1/2]

12.74.5.37seqarea_seq_x() [1/2]
12.74.5.38seqarea_seq_y() [1/2]
12.74.5.39mainwid_border() [1/2]
12.74.5.40mainwid_spacing() [1/2]
12.74.5.41mainwid_x()
12.74.5.42mainwid_y()
12.74.5.43control_height() [1/2]
12.74.5.44zoom() [1/2]
12.74.5.45zoom() [2/2]
12.74.5.46global_seq_feature() [1/2]
12.74.5.47global_seq_feature() [2/2]
12.74.5.48seqedit_scale() [1/2]
12.74.5.49seqedit_scale() [2/2]
12.74.5.50seqedit_key() [1/2]
12.74.5.51seqedit_key() [2/2]
12.74.5.52seqedit_bgsequence() [1/2]
12.74.5.53seqedit_bgsequence() [2/2]
12.74.5.54use_new_font() [1/2]
12.74.5.55allow_two_perfedits() [1/2]
12.74.5.5@perf_h_page_increment() [1/2]
12.74.5.57perf_v_page_increment() [1/2]
12.74.5.5&progress_bar_colored() [1/2]
12.74.5.59progress_bar_thick() [1/2]
12.74.5.6@nverse_colors() [1/2]
12.74.5.61window_redraw_rate() [1/2]
12.74.5.62use_more_icons() [1/2]
12.74.5.63save_user_config() [1/2]
12.74.5.64save_user_config() [2/2]
12.74.5.65grid_brackets() [2/2] 797
12.74.5.66grid_style() [2/2]

12.74.5.67mainwnd_rows() [2/2]
12.74.5.68mainwnd_cols() [2/2]
12.74.5.69max_sets() [2/2]
12.74.5.70text_x() [2/2]
12.74.5.71text_y() [2/2]
12.74.5.72seqchars_x() [2/2]
12.74.5.73seqchars_y() [2/2]
12.74.5.74seqarea_x() [2/2]
12.74.5.75seqarea_y() [2/2]
12.74.5.76seqarea_seq_x() [2/2]
12.74.5.77seqarea_seq_y() [2/2]
12.74.5.78mainwid_border() [2/2]
12.74.5.79mainwid_spacing() [2/2]
12.74.5.80control_height() [2/2]
12.74.5.81dump_summary()
12.74.5.82midi_ppqn() [1/2]
12.74.5.83midi_beats_per_bar() [1/2]
12.74.5.84midi_beats_per_minute() [1/2]
12.74.5.85midi_beat_width() [1/2]
12.74.5.86midi_buss_override() [1/2]
12.74.5.87min_zoom()
12.74.5.88max_zoom()
12.74.5.89baseline_ppqn()
12.74.5.90use_new_font() [2/2]
12.74.5.91allow_two_perfedits() [2/2]
12.74.5.92perf_h_page_increment() [2/2]
12.74.5.93perf_v_page_increment() [2/2]
12.74.5.94progress_bar_colored() [2/2]
12.74.5.95progress_bar_thick() [2/2]
12.74.5.96nverse_colors() [2/2]

12.74.5.97window_redraw_rate() [2/2]
12.74.5.9&use_more_icons() [2/2]
12.74.5.99midi_ppqn() [2/2]
12.74.5.10@idi_buss_override() [2/2]
12.74.5.101hidi_beats_per_bar() [2/2]
12.74.5.102bidi_beats_per_minute() [2/2]
12.74.5.10aidi_beat_width() [2/2]
12.74.5.10pdrivate_bus()
12.74.5.10 <u>f</u> rivate_instrument()
12.74.6 Friends And Related Function Documentation
12.74.6.1 userfile
12.74.7 Field Documentation
12.74.7.1 m_midi_buses
12.74.7.2 m_instruments
12.74.7.3 m_grid_style
12.74.7.4 m_grid_brackets
12.74.7.5 m_mainwnd_rows
12.74.7.6 m_mainwnd_cols
12.74.7.7 m_max_sets
12.74.7.8 m_mainwid_border
12.74.7.9 m_mainwid_spacing
12.74.7.10m_control_height
12.74.7.11m_current_zoom
12.74.7.12m_global_seq_feature_save
12.74.7.13m_seqedit_scale
12.74.7.14m_seqedit_key
12.74.7.15m_seqedit_bgsequence
12.74.7.16m_use_new_font
12.74.7.17m_allow_two_perfedits
12.74.7.18m_h_perf_page_increment

12.74.7.19m_v_perf_page_increment	806
12.74.7.20m_progress_bar_colored	806
12.74.7.21m_progress_bar_thick	806
12.74.7.22m_inverse_colors	806
12.74.7.23m_window_redraw_rate_ms	806
12.74.7.24m_use_more_icons	807
12.74.7.25m_text_x	807
12.74.7.26m_text_y	807
12.74.7.27m_seqchars_x	807
12.74.7.28m_seqchars_y	807
12.74.7.29m_midi_ppqn	807
12.74.7.30m_midi_beats_per_measure	808
12.74.7.31m_midi_beats_per_minute	808
12.74.7.32m_midi_beat_width	808
12.74.7.33m_midi_buss_override	808
12.74.7.34m_total_seqs	808
12.74.7.35m_seqs_in_set	808
12.74.7.36m_gmute_tracks	809
12.74.7.37m_max_sequence	809
12.74.7.38m_seqarea_x	809
12.74.7.39m_seqarea_y	809
12.74.7.40m_seqarea_seq_x	809
12.74.7.41m_seqarea_seq_y	809
12.74.7.42m_mainwid_x	809
12.74.7.43m_mainwid_y	810
12.74.7.44m_save_user_config	810
12.74.7.45mc_min_zoom	810
12.74.7.46mc_max_zoom	810
12.74.7.47mc_baseline_ppqn	810
12.75seq64::userfile Class Reference	811
12.75.1 Constructor & Destructor Documentation	812
12.75.1.1 userfile()	812
12.75.1.2 ∼userfile()	812
12.75.2 Member Function Documentation	812
12.75.2.1 parse()	812
12.75.2.2 write()	812
12.75.2.3 dump_setting_summary()	813

Chapter 1

Sequencer64

Author(s) Chris Ahlstrom 2015-11-27

1.1 Introduction

Sequencer64 is a major cleanup, refactoring, and documentation of the Seq24 live-play MIDI sequencer.

The current document, generated by Doxygen, describes the functions, classes, modules, and other entities used in this project.

Also read the ROADMAP, README, and contrib/bugs_to_investigate files to understand the genesis of this project and the things that still need to be done with Sequencer64.

Also, we have pretty deeply documented *Seq24* and *Sequencer64* with PDF files that can be generated by git-cloning the following projects, installing a number of tools related to PDF and LaTeX, and running "make":

- https://github.com/ahlstromcj/seg24-doc.git
- https://github.com/ahlstromcj/sequencer64-doc.git

These project also have prebuilt PDFs should one not want to bother building them.

In the present document, we've left out a fair amount of side-code to cut down on the size of the document. For example, the main module, redundant Windows support, utility headers like easy_macros.h, standard stuff like the mutex module, the fruity variants (at least the ones already refactored into their own modules), etc., are all left out. Still, the resulting PDF is over 300 pages long.

Some useful references:

- http://acad.carleton.edu/courses/musc108-00-f14/pages/04/04StandardMID← IFiles.html
- http://www.midimusicadventures.com/qs/midi-zips/soundtracks/kq6gm.zip

2 Sequencer64

Chapter 2

MIDI File Parsing in Sequencer64

Author(s) Chris Ahlstrom 2016-02-13

2.1 Introduction

This section describes the parsing of a MIDI file (and a few other topics). We wanted to add the reading of SMF 0 files to *Sequencer64*. We started with the main format that is supported, SMF 1. Once we understood that we, we figured out how to split a SMF 0 tracks correctly.

We split the midifile::parse() function into two sections. The first section analyzes the header of the MIDI. Then, based on whether the file is SMF 1 (the normal case) or SMF 0, either the parse_smf_1() function of or the parse—smf_0() function is called. The parse_smf_0() function creates one sequence object per channel present in the SMF 0 file, plus the original track. The last pattern slot (sequence 16) will contain the original track data, and the rest will contain common data and then channel data for each channel. After the parsing is done, all the tracks (including the original track) will be added to the performance. The user then has the option of deleting the original track, which will be the last track.

2.2 SMF 1 Parsing

This section describes the parsing of the header chunk, MThd, and the track chunk, MTrk.

The midifile::parse() function starts by opening the MIDI file, getting its file-size, pre-allocating the data vector to that size, reading all of the characters into that vector, and then closing the file.

2.2.1 MIDI File Header, MThd

The data of the header is read:

```
Header ID: "MThd" read_long() 4 bytes
MThd length: 6 read_long() 4 bytes
Format: 0, 1, 2 read_short() 2 bytes
No. of track: 1 or more read_short() 2 bytes
PPQN: 192 read_short() 2 bytes
```

The header ID and it's length are always the same values. The formats that Sequencer64 supports are 0 or 1. SMF 0 has only one track, while SMF 1 can support an arbitary number of tracks. The last value in the header is the PPQN value, which specifies the "pulses per quarter note", which is the basic time-resolution of events in the MIDI file. Common values are 96 or 192, but higher values are also common. Sequencer64 and its precursor, Seq24, default to 192.

2.2.2 MIDI Track, MTrk

Sequencer64 next reads the tracks specified in the file. Each track is assumed to cover a different MIDI channel, but always the same MIDI buss. (The MIDI buss is not a data item in standard MIDI files, but it is a special data item in Seq24/Sequencer64 MIDI files.) Each track is tagged by a standard chunk marker, "MTrk". Other markers are possible, and are to be ignored, if nothing else. Here are the values read at the beginning of a track:

```
Track ID: "MTrk" read_long() 4 bytes
Track length: varies read_long() 4 bytes
```

The track length is the number of bytes that need to be read in order to get all of the data in the track.

Next, a new sequence object is created, with the PPQN value passed to its constructor. The sequence then is hooked to the master MIDI buss object. The "RunningTime" accumulator is set to 0 for that track.

Next, the parse() function loops through the rest of the track, reading data and logging it to the sequence. Let's go through the loop, which is the meat of the processing.

TODO: An empty event is created before track processing, and re-used for every track and event. This seems dangerous. We moved the event constructor two levels of nesting deeper, and it seems to work fine.

Delta time. The amount time that passes from one event to the next is the *delta time*. For some events, the time doesn't matter, and is set to 0. This values is a *variable length value*, also known as a "VLV" or a "varinum". It provides a way of encoding arbitrarily large values, a byte at a time. For now, just note that a varinum is 1 or more bytes, and MIDI provides a way to tell when the varinum is complete.

```
Delta time: varies read_varinum() 1 or more bytes
```

2.2.2.1 Channel Events

Status. The byte after the delta time is examined by masking it against 0x80 to check the high bit. If not set, it is a "running status", it is replaced with the "last status", which is 0 at first.

```
Status byte: varies read_byte() 1 byte
```

If the high bit is set, it is a status, and is passed to the setter $event::set_status()$.

The "RunningTime" accumulator is incremented by the delta-time. The current time is adjusted as per the PPQN ratio, if needed, and passed to the setter $event::set_timestamp()$.

Now what does the status mean? First, the channel part of the status is masked out using the 0xF0 mask.

If it is a 2-data-byte event (note on, note off, aftertouch, control-change, or pitch-wheel), then the two data bytes are read:

```
Data byte 0: varies read_byte() 1 byte
Data byte 1: varies read_byte() 1 byte
```

If the status is a note-on event, with data[1] = 0, then it is converted to a note-off event, a fix for the output quirks of some MIDI devices, and the status of the event is amended to EVENT_NOTE_OFF.

If it is a 1-data-btye event (program change or channel pressure), then only data byte 0 is read.

Then the one or two data bytes are added to the event by overloads of event::set_data(), the event is added to the current sequence by sequence::add_event(), and the MIDI channel of the sequence is set by sequence::set_midi_channel().

Note that this is the point where parsing could detect a change in channel, and select a new sequence to support that channel, and add the events to that sequence, if the file were SMF 0.

Also note that the channel of the sequence is set every a new channel event/status is read. This should be done once, and then simply warned about if a non-matching channel occurs.

Lastly, note that it might be better to do the sequence function calls at the end of processing the event.

2.2 SMF 1 Parsing 5

2.2.2.2 Meta Events

If the event status masks off to 0xF0 (0xF0 to 0xFF), then it is a meta event. If the status is 0xFF, it is called a "Sequencer-specific", or "SeqSpec" event. For this kind of event, then a type byte and the length of the event are read.

```
Meta type: varies read_byte() 1 byte
Meta length: varies read_varinum() 1 or more bytes
```

If the type of the SeqSpec (0xFF) meta event is 0x7F, parsing checks to see if it is one of the Seq24 "proprietary" events. These events are tagged with various values that mask off to 0x24240000. The parser reads the tag:

```
Prop tag: 0x242400nn read_long() 4 bytes
```

These tags provide a way to save and recover Seq24/Sequencer64 properties from the MIDI file: MIDI buss, MIDI channel, time signature, sequence triggers, and (new), the key, scale, and background sequence to use with the track/sequence. Any leftover data for the tagged event is let go. Unknown tags ate skipped.

If the type of the SeqSpec (0xFF) meta event is 0x2F, then it is the End-of-Track marker. The current time is set using $sequence::set_length()$ and then $sequence::zero_markers()$ is called, and parsing is done for that track.

If the type of the SeqSpec (0xFF) meta event is 0x03, then it is the sequence name. The "length" number of bytes are read, and loaded by $sequence::set_name()$.

If the type of the SeqSpec (0xFF) meta event is 0x00, then it is the sequence number, which is read:

```
Seq number: varies read_short() 2 bytes
```

Note that the sequence number might be modified latter to account for the current screenset in force for a file import operation.

Anything other SeqSpec type is simply skipped by reading the "length" number of bytes.

To summarize the process, here are the relevant event and sequence setter calls typically made while parsing a MIDI track:

```
1. perform::add_sequence()
   (a) sequence::sequence()
   (b) sequence::set_master_midi_bus())
   (c) sequence::add_event()
        i. event::event()
        ii. event::set_status()
        iii. event::set_timestamp()
        iv. event::set_data()
   (d) sequence::set_midi_channel()
        (e) sequence::set_length()
        (f) sequence::set_name()
        (g) sequence::set_midi_bus()
2. xxxxx::yyyy()
```

2.2.3 Meta Events Summary

Here, we summarize the MIDI meta events for your edification.

```
1. FF 00 02 ssss: Sequence Number.
```

- 2. FF 01 len text: Text Event.
- 3. FF 02 len text: Copyright Notice.
- 4. FF 03 len text: Sequence/Track Name.
- 5. FF 04 len text: Instrument Name.
- 6. FF 05 len text: Lyric.
- 7. FF 06 len text: Marker.
- 8. FF 07 len text: Cue Point.
- 9. FF 08 len text: Patch/program Name.
- 10. FF 09 len text: Device Name.
- 11. FF 0A through 0F len text: Other kinds of text events.
- 12. FF 20 01 cc: MIDI channel (obsolete, used by Cakewalk)
- 13. FF 21 01 pp: MIDI port (obsolete, used by Cakewalk)
- 14. FF 2F 00: End of Track.
- 15. FF 51 03 tttttt: Set Tempo, us/qn.
- 16. FF 54 05 hr mn se fr ff: SMPTE Offset.
- 17. FF 58 04 nn dd cc bb: Time Signature.
- 18. FF 59 02 sf mi: Key Signature.
- 19. FF 7F len data: Sequencer-Specific.

The next sections describe the events that Sequencer tries to handle. These are

- Sequence Number (0x00)
- Track Name (0x03)
- End-of-Track (0x2F)
- Set Tempo (0x51) (Sequencer64 only)
- Time Signature (0x58) (Sequencer64 only)
- Sequencer-Specific (0x7F)
- System Exclusive (0xF0) Sort of handled, functionality incomplete..

2.2.3.1 Sequence Number (0x00)

```
FF 00 02 ss ss
```

This optional event must occur at the beginning of a track, before any non-zero delta-times, and before any transmittable MIDI events. It specifies the number of a sequence.

2.2 SMF 1 Parsing 7

2.2.3.2 Track/Sequence Name (0x03)

```
FF 03 len text
```

If in a format 0 track, or the first track in a format 1 file, the name of the sequence. Otherwise, the name of the track.

2.2.3.3 End of Track (0x2F)

```
FF 2F 00
```

This event is not optional. It is included so that an exact ending point may be specified for the track, so that it has an exact length, which is necessary for tracks which are looped or concatenated.

2.2.3.4 Set Tempo Event (0x51)

The MIDI Set Tempo meta event sets the tempo of a MIDI sequence in terms of the microseconds per quarter note. This is a meta message, so this event is never sent over MIDI ports to a MIDI device.

After the delta time, this event consists of six bytes of data:

```
FF 51 03 tt tt tt
```

Example:

```
FF 51 03 07 A1 20
```

- 1. 0xFF is the status byte that indicates this is a Meta event.
- 2. 0x51 the meta event type that signifies this is a Set Tempo event.
- 3. 0x03 is the length of the event, always 3 bytes.
- 4. The remaining three bytes carry the number of microseconds per quarter note. For example, the three bytes above form the hexadecimal value 0x07A120 (500000 decimal), which means that there are 500,000 microseconds per quarter note.

Since there are 60,000,000 microseconds per minute, the event above translates to: set the tempo to 60,000,000 / 500,000 = 120 quarter notes per minute (120 beats per minute). This is a 24-bit binary value, so each byte covers the full range of 0x00 to 0xFF.

This event normally appears in the first track. If not, the default tempo is 120 beats per minute. This event is important if the MIDI time division is specified in "pulses per quarter note", which does not itself define the length of the quarter note. The length of the quarter note is then determined by the Set Tempo meta event.

Representing tempos as time per beat instead of beat per time allows absolutely exact DWORD-term synchronization with a time-based sync protocol such as SMPTE time code or MIDI time code. This amount of accuracy provided by this tempo resolution allows a four-minute piece at 120 beats per minute to be accurate within 500 usec at the end of the piece.

We have now added the Tempo meta event (and the Time Signature meta event) to the track, which allows other sequencers to obtain these values from a Sequencer64 MIDI file. Here are the original headers for a normal MIDI file and its legacy (Seq24) conversion, as shown by the midicvt application:

```
hymne.asc
                                        hymne-ppqn-384.asc
MThd 1 4 96
                                        MThd 1 4 384
                                        MTrk
0 Meta SeqName "Vangelis: Hymne"
                                        0 SeqNr 0
0 TimeSig 4/4 24 8
                                        0 Meta SeqName "Vangelis: Hymne"
                                       0 SeqSpec 24 24 00 08 (no triggers)
0 SeqSpec 24 24 00 01 00 (MIDI buss 0)
0 Tempo 750000
0 Meta TrkEnd
                                        0 SeqSpec 24 24 00 06 04 04 (beats, width)
TrkEnd
                                        0 SeqSpec 24 24 00 02 00 (MIDI ch. 0)
                                        96 Meta TrkEnd
                                        TrkEnd
```

Here is the header data that result from the new conversion, which is used if the "legacy" option is not in force:

```
MThd 1 4 192
MTrk
0 SeqNr 0
0 Meta SeqName "Vangelis: Hymne"
0 TimeSig 4/4 24 8
0 Tempo 750000
0 SeqSpec 24 24 00 08
0 SeqSpec 24 24 00 01 00
0 SeqSpec 24 24 00 06 04 04
0 SeqSpec 24 24 00 02 00
48 Meta TrkEnd
TrkEnd
```

2.2.3.5 Time Signature Event (0x58)

After the delta time, this event consists of seven bytes of data:

```
FF 58 04 nn dd cc bb
```

The time signature is expressed as four numbers. nn and dd represent the numerator and denominator of the time signature as it would be notated. The numerator counts the number of beats in a measure (beats per measure or beats per bar). The denominator is a negative power of two: 2 represents a quarter-note, 3 represents an eighthnote, etc. The denominator specifies the unit of the beat (e.g. 4 or 8). In Seq24/Sequencer64, this value is also called the "beat width".

The CC parameter expresses the number of MIDI clocks (or "ticks", or "pulses") in a metronome click. The standard MIDI clock ticks 24 times per quarter note, so a value of 6 would mean the metronome clicks every 1/8th note. A CC value of 6 would mean that the metronome clicks once every 1/8th of a note (quaver). This MIDI clock is different from the clock (PPQN) that determines the start time and duration of the notes.

The bb parameter expresses the number of notated 32nd-notes in a MIDI quarter note (24 MIDI Clocks). The usual value for this parameter is 8, though some sequencers allow the user to specify that what MIDI thinks of as a quarter note, should be notated as something else. For example, a value of 16 means that the music plays two quarter notes for each quarter note metered out by the MIDI clock, so that the music plays at double speed.

Examples:

```
FF 58 04 04 02 18 08
```

- 1. 0xFF is the status byte that indicates this is a Meta event.
- 2. 0x58 the meta event type that signifies this is a Time Signature event.

2.2 SMF 1 Parsing 9

- 3. 0x04 is the length of the event, always 4 bytes.
- 4. 0x04 is the numerator of the time signature, and ranges from 0x00 to 0xFF.
- 5. 0x02 is the log base 2 of the denominator, and is the power to which 2 must be raised to get the denominator. Here, the denominator is 2 to 0x02, or 4, so the time signature is 4/4.
- 6. 0x18 is the metronome pulse in terms of the number of MIDI clock ticks per click. Assuming 24 MIDI clocks per quarter note, the value here (0x18 = 24) indidicates that the metronome will tick every 24/24 quarter note. If the value of the sixth byte were 0x30 = 48, the metronome clicks every two quarter notes, i.e. every half-note.
- 7. 0x08 defines the number of 32nd notes per beat. This byte is usually 8 as there is usually one quarter note per beat, and one quarter note contains eight 32nd notes.

A time signature of 6/8, with a metronome click every 3rd 1/8 note, would be encoded:

```
FF 58 04 06 03 24 08
```

Remember, a 1/4 note is 24 MIDI Clocks, therefore a bar of 6/8 is 72 MIDI Clocks. Hence 3 1/8 notes is 36 (=0x24) MIDI Clocks.

There should generally be a Time Signature Meta event at the beginning of a track (at time = 0), otherwise a default 4/4 time signature will be assumed. Thereafter they can be used to effect an immediate time signature change at any point within a track.

For a format 1 MIDI file, Time Signature Meta events should only occur within the first MTrk chunk.

If a time signature event is not present in a MIDI sequence, 4/4 signature is assumed.

In Sequencer64, the c_timesig SeqSpec event is given priority. The conventional time signature is used only if the c_timesig SeqSpec is not present in the file. NEEDS TO BE TESTED.

```
2.2.3.6 SysEx Event (0xF0)
```

If the meta event status value is 0xF0, it is called a "System-exclusive", or "SysEx" event.

```
F0 len data F7
```

Sequencer64 has some code in place to store these messages, but the data is currently not actually stored or used. Although there is some infrastructure to support storing the SysEx event within a sequence, the SysEx information is simply skipped. Sequencer64 warns if the terminating 0xF7 SysEx terminator is not found at the expected length. Also, some malformed SysEx events have been encountered, and those are detected and skipped as well.

2.2.3.7 Sequencer Specific (0x7F)

This data, also known as SeqSpec data, provides a way to encode information that a specific sequencer application needs, while marking it so that other sequences can safely ignore the information.

```
FF 7F len data
```

In *Seq24* and *Sequencer64*, the data portion starts with four bytes that indicate the kind of data for a particular SeqSpec event:

In Seq24, these events are placed at the end of the song, but are not marked as SeqSpec data. Most MIDI applications handle this situation fine, but some (e.g. midicvt) do not. Therefore, Sequencer64 makes sure to wrap each data item in the 0xFF 0x7F wrapper.

Also, the last three items above (key, scale, and background sequence) can also be stored (by *Sequencer64*) with a particular sequence/track, as well as at the end of the song. Not sure if this bit of extra flexibility is useful, but it is there.

2.2.3.8 Non-Specific End of Sequence

Any other statuses are deemed unsupportable in Sequencer64, and abort parsing with an error.

If the —bus option is in force, sequence::set_midi_bus() is called to override the buss number (if any) stored with the sequence.

Finally, $perform::add_sequence()$ adds the sequence to the encoded tune.

2.3 SMF 0 Parsing

After parsing SMF 1 track data, we end up with a number of sequences, each on a different MIDI channel. With SMF 0, data for all channels is present in a single track. Sequencer64 will read SMF 0 data, but we really need to be able to have one MIDI channel per track. So we need to take the data from the sequence and use it to make more sequences.

```
sequence::add_event().
sequence::set_midi_channel().
sequence::set_length().
sequence::set_midi_bus().
perform::add_sequence().
```

This code basically works. For now, please look at the source code for more details. Also, the reading of SMF 0 MIDI files is described in the *sequencer64-doc* project on GitHub.

2.4 Running Status

2.4 Running Status

When we apply the midicvt application to a file saved by Sequencer64, we can end up with a successful ASCII conversion that ends with an error message:

```
$ midicvt hymne-seq64.midi -o hymne-seq64.asc
? Error at MIDI file offset 12155 [0x2f7b]
Error: Garbage at end 'readtrack(): unexpected running status'
```

Is this a problem in midicvt or Sequencer4? Let's learn about running status.

Running status is a way to speed up the sending of MIDI bytes to a synthesizer or sequencer by taking advantage of redundancy where possible. For example, if we're sending a consecutive group of Note On and Note Off messages to a particular channel, we can save some time by not sending the channel status byte after the first time. Here's an example with Note On on channel 1:

```
0x90 3C 7F
0x90 40 7F
0x90 43 F3
```

Since no change in status occurs after the first of these three events, we can drop the subsequent status bytes:

```
0x90 3C 7F
40 7F
43 F3
```

The 0x90 byte is saved in a "running status buffer" (RSB), and is filled in by the receiving device.

Here is the sequence of events for operating with running status.

- 1. Clear the RSB buffer (RSB = 0) to start.
- 2. If a **Voice Category Status** (VCS) byte is received, then set RSB = VCS. VCS bytes range from 0x80 to 0xEF. This is binary 1000000 to 11100000.
- 3. If a data byte is received (data bytes range from 0x00 to 0x7F, binary 0000000 to 0111111; that is, bit 7 is always 0 in a data byte):
 - (a) If RSB != 0, first insert the RSB into the incoming data stream, then insert the data byte.
 - (b) If RSB == 0, then just insert the data byte into the incoming data stream.
- 4. Clear the RSB buffer (RSB = 0) when a System Common Message (SCM) status byte is received. SCM bytes range from 0xF0 to 0xF7.
- 5. The message after an SCM must begin with a status byte. That is a byte with bit 7 set.
- 6. Do no special action when a Realtime Category Message (RCM) byte is received. RCM bytes range from 0xF8 to 0xFF.

Note that some events, such as Tempo, assume that its bytes are all data bytes.

Chapter 3

JACK, Live, and Song Modes in Sequencer64

Author(s) Chris Ahlstrom 2016-08-18

3.1 Introduction

This section describes the interactions between JACK settings and the Live/Song Mode settings, with an eye to describing the proper behavior of Sequencer64 with JACK settings, how the Live/Song modes are supposed to work, and what bugs or issues remain in Sequencer64's JACK handling.

I'm not sure why Doxygen is applying the "code" font so often here. Weird, annoying.

3.2 JACK Functions

Please study the following URL and note these important points:

http://jackaudio.org/files/docs/html/transport-design.html

- The timebase master continuously updates position information, beats, timecode, etc. There is at most one
 master active at a time. If no client is registered as timebase master, frame numbers will be the only position
 information available.
- The timebase master registers a callback that updates position information while transport is rolling. Its output affects the following process cycle. This function is called immediately after the process callback in the same thread whenever the transport is rolling, or when any client has set a new position in the previous cycle.
- Clients that don't declare a sync callback are assumed ready immediately, anytime the transport wants to start. If a client doesn't require slow-sync processing, it can set its sync callback to NULL.
- The transport state is always valid; initially it is JackTransportStopped.
- When someone calls <code>jack_transport_start()</code>, the engine resets the poll bits and changes to a new state, <code>JackTransportStarting</code>.
- · When all slow-sync clients are ready, the state changes to JackTransportRolling.

Does Sequencer64 need a latency callback?

http://jackaudio.org/files/docs/html/group__ClientCallbacks.html

(We need to see why most of the following is in a monospaced font. Is there a new Doxygen feature?)

Here are summaries of the JACK functions used in the jack_assistant module:

3.2.1 jack_client_open()

```
Open a client session with a JACK server. More complex and powerful than <tt>jack_client_new()</tt>.

Clients choose which of several servers to connect, and how to start the server automatically, if not already running. There is also an option for JACK to generate a unique client name.

const char * client_name, jack_options_t options, jack_status_t * status,
```

client_name of at most jack_client_name_size() characters. The name scope is local to each server. Unless forbidden by the JackUseExactName option, the server will modify this name to create a unique variant, if needed.

options formed by OR-ing together JackOptions bits. Only the JackOpenOptions bits are allowed.

status (if non-NULL) an address for JACK to return information from the open operation. This status word is formed by OR-ing together the relevant JackStatus bits.

Optional parameters: depending on corresponding [options bits] additional parameters may follow status (in this order).

[JackServerName] (char *) server_name selects from among several possible concurrent server instances. Server names are unique to each user. If unspecified, use "default" unless \$JACK_DEFAULT_SERVER is defined in the process environment.

Returns:

Opaque client handle if successful. If this is NULL, the open operation failed, and *status includes JackFailure, and the caller is not a JACK client.

3.2.2 jack_on_shutdown()

Registers a function to call when the JACK server shuts down the client thread. It must be an asynchonrous POSIX signal handler: only async-safe functions, executed from another thread. A typical function might set a flag or write to a pipe so that the rest of the application knows that the JACK client thread has shut down. Clients do not need to call this function. It only helps clients understand what is going on. It should be called before <tt>jack_client_activate()</tt>.

3.2.3 jack_set_sync_callback()

Register/unregister as a slow-sync client; it can't respond immediately to transport position changes. The callback is run at the first opportunity after registration: if the client is active, this is the next process cycle, otherwise it is the first cycle after <tt>jack_activate()</tt>. After that, it runs as per JackSyncCallback rules. Clients that don't set this callback are assumed ready immediately any time the transport wants to start.

3.2 JACK Functions 15

3.2.4 jack_set_process_callback()

Tells the JACK server to call the callback whenever there is work. The function must be suitable for real-time execution, it cannot call functions that might block for a long time: malloc(), free(), printf(), pthread_mutex_lock(), sleep(), wait(), poll(), select(), pthread_join(), pthread_cond_wait(), etc. In the current class, this function is a do-nothing function.

3.2.5 jack set session callback()

Tells the JACK server to call the callback when a session event is delivered. Setting more than one session callback per process is probably a design error. For a multiclient application, it's more sensible to create a JACK client with only one session callback.

3.2.6 jack_activate()

Tells the JACK server that the application is ready to start processing.

3.2.7 jack release timebase()

TODO

3.2.8 jack client close()

TODO

3.2.9 jack_transport_start()

Starts the JACK transport rolling. Any client can make this request at any time. It takes effect no sooner than the next process cycle, perhaps later if there are slow-sync clients. This function is realtime-safe. No return code.

3.2.10 jack_transport_stop()

3.2.11 jack_transport_locate()

Repositions the transport to a new frame number. May be called at any time by any client. The new position takes effect in two process cycles. If there are slow-sync clients and the transport is already rolling, it will enter the JackTransportStarting state and begin invoking their sync_callbacks until ready. This function is realtime-safe.

3.2.12 jack_transport_reposition()

```
Request a new transport position. May be called at any time by any client. The new position takes effect in two process cycles. If there are slow-sync clients and the transport is already rolling, it will enter the JackTransportStarting state and begin invoking their sync_callbacks until ready. This function is realtime-safe. This call, made in the position() function, is currently disabled.
```

3.2.13 jack transport query()

Query the current transport state and position. This function is realtime-safe, and can be called from any thread. If called from the process thread, pos corresponds to the first frame of the current cycle and the state returned is valid for the entire cycle.

The first parameter is the client, which is a pointer to the JACK client structure.

The second parameter is a pointer to structure for returning current transport position; pos->valid will show which fields contain valid data. If pos is NULL, do not return position information.

This function returns the current transport state.

3.3 Modes Operation

3.3.1 No JACK, Live Mode

In ~/.config/sequencer64/sequencer64.rc, set:

- jack_transport = 0
- jack_master = 0
- jack master cond = 0
- song_start_mode = 0

By changing the start mode to 0 (false), Sequencer64 is put into Live Mode. With this setting, control of the muting and unmuting of patterns resides in the main window (the patterns window). One can start the playback in the performance (song) window, but it will not affect which patterns play, at all.

Note that this option is part of the File / Options / JACK/LASH configuration page.

3.3.2 No JACK, Song Mode

In \sim /.config/sequencer64/sequencer64.rc, set:

- jack_transport = 0
- jack master = 0
- jack_master_cond = 0
- song_start_mode = 1

By changing the start mode to 1 (true), Sequencer64 is put into Song Mode.

With this setting, control of the muting and unmuting of patterns resides in the song window (the performance window). The patterns shown in the pattern slots of the main window turn on and off whenever the progress bar is in the pattern as drawn in the perforance window.

Note that this option is part of the File / Options / JACK/LASH configuration page.

3.4 Breakage 17

3.3.3 JACK Transport

In ~/.config/sequencer64/sequencer64.rc, set:

- jack_transport = 1
- jack_master = 0
- jack master cond = 0
- song_start_mode = 0 or 1 (see previous section)

The current behavior is that gjackctl and sequencer64 playback/progress seem to be independent of each other.

The workaround seems to be to set seq24/sequencer64 as JACK Master, or if another application (e.g. Qtractor) is JACK Master.

OLD BEHAVIOR:

```
Start qjackctl, verify that it sets up correctly, then click it's
"play" button to start the transport rolling. Run sequencer64, load a
file. Then note that starting playback (whether in the main window or
in the performance window) is ineffective, but resets the time counter
in qjackctl. Why? With JACK sync enabled by the macro:

[JACK transport slave]
    jack sync(): zero frame rate [single report]!?

[JackTransportRolling]
```

[JackTransportStarting] (every time space bar pressed)

END OF OLD BEHAVIOR.

3.4 Breakage

Old message about seq24 being broken:

[Start playback]

 $\verb|http://lists.linuxaudio.org/pipermail/linux-audio-user/2010-November/073848. \leftarrow \verb|html||$

```
i dont see the transport synchronisation working with a jackl svn version. you are still using only a sync callback.

and you are relying on the transport to go through the JackTransportStarting state.

this issue should be fixed.
iirc we came to the conclusion, that seq24 is broken, and we will not revert the changes in jack, which break it.

the quick and dirty fix on your side, would be to register an empty process_callback.

but the issue still remains. seq24 is NOT a slow sync client. but it registers a sync_callback.
and it even takes a lock in the sync callback.

the patch for jack-session support didnt get merged either.
```

Another one (no need for a URL):

I use seq24 for the majority of my projects but it isn't ideal (I should point out that I never finish anything). I don't like seq24's pianoroll editor, the way you do CC envelopes isn't ideal, it uses alsa-midi, there's unnecessary complexity in switching from pattern-trigger mode to song mode, and its insistence on being transport master while not even being able to adjust tempo when live is annoying

3.5 JACK References

- $\bullet \ \texttt{http://libremusicproduction.com/articles/demystifying-jack-\$E2\$80\$93-beginners-guident and the production of the$
- http://jackaudio.org/files/docs/html/transport-design.html
- http://kxstudio.linuxaudio.org/Repositories

Chapter 4

User Testing of Sequencer64 with Yoshimi

Author(s) Chris Ahlstrom 2016-03-04

4.1 Introduction

This section describes user testing of Sequencer64 using Yoshimi. It will expand as we work our way through all the many use-cases that can be achieved with Sequencer64 and Yoshimi.

Please note that the most advanced and recent testing can be found currently in the document contrib/notes/jack-testing txt. We will eventually merge the final tests here... someday.

4.2 Smoke Test

Every so often we run Sequencer64 with a software synthesizer to make sure we haven't broken any functionality via our major refactoring efforts. We call it a "smoke test". We fire up the two application, and see if anything smokes.

This smoke test sets up Yoshimi with a very simple ALSA setup, and no instruments are loaded. Instead, only the "Simple Sound" is used on all channels. We've been doing this test with Yoshimi 1.3.6. The current Debian Sid ("testing") version of Yoshimi is 1.3.6-2, pulled from SourceForge. It seems to have issues, so we've been cloning and pulling the code from:

```
https://github.com/Yoshimi/yoshimi.git
```

After getting the application build and installed, the next step is to run it, using ALSA for MIDI and for audio:

```
$ yoshimi -a -A &
```

Next, fix up the configuration files for Sequencer64, \sim /.config/sequencer64/sequencer64.rc and \sim /.config/sequencer64/sequencer64.usr.

First hide sequencer64.usr somewhere, or delete it, as it will determine what MIDI devices are available, and we don't want that (yet). Second, make sure that sequencer64.rc makes the following setting:

```
[manual-alsa-ports]
# Set to 1 if you want sequencer64 to create its own ALSA ports and
# not connect to other clients
0  # number of manual ALSA ports
```

Next, run the newly-built version of Sequencer64. If desired, use the –bus option described below to force the buss number to the buss you need, as shown in the second version of the command:

```
$ sequencer64/sequencer64 &
$ sequencer64/sequencer64 --bus 5 &
```

In File / Options / MIDI Clock, observe the MIDI inputs made available by your system. Our system shows:

```
[0] 14:0 (Midi Through Port-0)

[1] 128:0 (TiMidity port 0)

[2] 128:0 (TiMidity port 1)

[3] 128:0 (TiMidity port 2)

[4] 128:0 (TiMidity port 3)

[5] 129:0 (input)
```

For some reason (a bug in Yoshimi?), input "[5]" doesn't indicate that it is Yoshimi, but it is. Take note of that input number... that is the MIDI buss number that is needed to drive Yoshimi.

Also make sure that of the clock settings for those busses are "Off".

The next instruction still works, but it is easier to simply pass the option -bus 5 to Sequencer64 when starting it up.

Now open the file sequencer64/contrib/midi/b4uacuse-GM-format.midi in Sequencer64. For all of the patterns (slots) that have lots of data in them, right click on the pattern and select *Midi Bus / [5] 129:0 (input)* and the desired channel number. (Doesn't matter much, just use up the lower channel numbers first).

Back in Yoshimi, select each Part corresponding to the channels you selected. Make sure *Enabled* is checked for each desired channel.

Back in Sequencer64, click on each pattern you want to hear, which highlights them in black. Now click the play button (green triangle). The song should play, with each part using the "Simple Sound". Not too bad for a bunch of sine waves, eh?

Now we can test the application more fully. Note that the instructions here are very light. Detailed instructions on the usage of Sequencer64 can be found in the following project, which contains a PDF file and the LaTeX code used to build it:

```
https://github.com/ahlstromcj/sequencer64-doc.git
```

Although it applies to an earlier version of the project, it still mostly holds true for Sequencer64.

4.3 Tests in the Patterns Window

The Patterns window is the inside portion of the main window, supported by the mainwid class. it contains a grid of boxes or slots, with each slot potentially containing a pattern, sequence, or track. Empty tracks (i.e. tracks that contain no events, like title-only tracks) are highlighted in yellow.

This window supports only a single variant of mouse-handling.

4.3.1 Button Clicks on a Pattern

A left-click on a pattern slot should cause the following to happen:

- 1. The pattern will be highlighted (white on a black background). This won't occur until the button is released.
- 2. During playback, the pattern will emit MIDI events and play its sequence.
- 3. If the pattern is dragged to another slot, whether playing is in progress or not, releasing the button in the destination slot will move the pattern to that slot.

A right-click on a pattern slot should cause the following to happen:

- 1. If the pattern is empty, then a pop-up menu to make a New pattern, paste a pattern, or make other selections will appear.
- 2. If the pattern is active, then a pop-up menu to Edit the pattern or make other selections will appear.
- 3. A second right-click, just off the menu, will dismiss the menu.

4.3.2 Patterns Window Key Shortcuts

First, note the selection of the File / Options / Keyboard / Show keys option. The tests here should work whether or not it is selected. The only difference is if the keys are shown.

We got a segfault during this test, when we weren't being systematic about it.

4.3.3 The Sequencer64 User File

To be discussed.

4.4 Tests Using Valgrind

Valgrind is a very useful tool for unearthing memory issues and other issues in an application, especially when one has the source code and can build the code with debugging information.

One runs the application from the command line, preceding its command line with valgrind and some of its options.

4.4.1 Valgrind Suppressions

One problem with valgrind is that it also uncovers errors in system libraries that one has no control over. These errors clutter the output, so we suppress them using a valgrind "suppressions" file. Here's how to create one:

```
$ valgrind --gen-suppressions=yes --log-file=val.supp ./Sequencer64/sequencer64
$ valgrind --gen-suppressions=all --log-file=val.supp ./Sequencer64/sequencer64
```

As the program runs, one is asked to print a suppression. If the error is due to a system or third-party library, answer "Y return", and then copy-and-paste the suppression to a file, giving it a name. For example, we provide a file contrib/seq64.supp containing suppressions of errors that annoy us. There are way too many "errors" in ALSA, GTK+, gtkmm, glibc, and more.

The second command collects all the suppressions. Passing the val.supp file through sed makes it immediately usable:

```
$ sed -i -e /^==/g val.supp
```

Running valgrind like this then shows mostly the errors we care about:

```
$ valgrind --suppressions=val.supp ./Sequencer64/sequencer64
```

We've added some other suppression files to the contrib directory. Too much! For example:

```
https://github.com/dtrebbien/GNOME.supp
```

However, overall this process is very painful, and we're going to eventually do all the valgrind work on the unit-test project for Sequencer64:

```
https://github.com/ahlstromcj/seq64-tests
```

4.4.2 Full Valgrind Leak-Checking

Here's how to capture errors, while suppressing the system errors and while generating a log file:

```
$ valgrind --suppressions=contrib/seq64.supp --leak-check=full \
    --track-origins=yes --log-file=valgrind.log --show-leak-kinds=all \
    ./Sequencer64/sequencer64
```

The errors can be also be re-routed to a log-file via the "2> valgrind.log" shell redirection.

Another idea is to precede the valgrind command with the following construct:

```
$ G_SLICE=debug-blocks valgrind ...
```

G_SLICE=debug-blocks will turn off gtk's advanced memory management to allow valgrind to show correct results. This results in an amazing plethora or invalid read and invalid write errors in GNOME-related libraries. Sheesh!

And don't forget about Valgrind's "massif" memory-tracking tool! (More to come!)

4.4.2.1 Leak-Checking Basic Operation

For the first pass, just run Sequencer64, then immediately exit. Then scan the log file to see if any "errors" can be pinpointed to the application and library code.

Don't forget to run the same scenario without valgrind, in a console window, to see if any of our own debug/problem output occurs.

In any case, leakage tagged as "still reachable" isn't as bad as leakage tagged as "definitely lost" or "indirectly lost".

But good luck finding a Sequencer64 bug buried in the chaff of 3rd-party valgrind reports, even with some suppressions enabled. Apparently a lot of them have to do with data structures that are intended to last the full life of the application.

One can make the search a little easier by searching for the "seq64" namespace in the valgrind log.

4.5 Specific Fault Debugging

This section goes through specific debugging cases we encountered. They should be part of the regular testing of Sequencer64.

4.6 Snipping of a MIDI file.

In order to have a test file for the *seq64-tests* project, we loaded up the b4uacuse-GM-format.midi file, removed all but four of the tracks, and saved it as b4uacuse-snipped.midi. Loading this file into Sequencer64 caused the following:

```
$ ./Sequencer64/sequencer64
[Reading user configuration /home/ahlstrom/.config/sequencer64/sequencer64.usr]
[Reading rc configuration /home/ahlstrom/.config/sequencer64/sequencer64.rc]
get_sequence(): m_seqs[4] not null
Segmentation fault
```

First step, fire up a debugger and see what happened. We use cgdb, a text-based front-end for gdb with a "vi" feel.

```
$ cgdb ./Sequencer64/sequencer64
```

Just hit "r", do File / Open, navigate to b4uacuse-snipped.midi, select it, and watch what happens.

The "bt" (backtrace) command shows a pretty large stack, 52 items. Page up to the top of the stack, and select frame 1 ("fr 1"). This shows a mutex at a very low address, 0x650! Frame 2 shows we are in the automutex constructor, calling lock() on that same badly-located mutex. Frame 3 is in sequence::event_count(), same bad mutex, and the m_events member is at address 0x0. Obviously, we're dealing with an unallocated sequence.

Frame 4 is in mainwid::draw_sequence_on_pixmap(), just after we've retrieved the next sequence via perform ::get_sequence(4). But that would be the fifth sequence (the sequence numbers start at 0), and we snipped all but 4 from the file before we saved it.

So, one thing we need to do is *check* the value returned by get_sequence() before we try to use it. The other thing to do is figure out how we got to the fifth sequence, and fix that code as well. Using the command "p perf(). \leftarrow sequence_count()", we verify that there are indeed only 4 sequences allocated.

Frame 5 is in mainwid::draw_sequences_on_pixmap(). That function tries to load all sequences on the current screen-set, from 0 to 31, without checking to see how many their actually are. Inefficient and dangerous.

Frame 6 is in mainwid::reset(). We could pass perf().sequence_count() here for checking, or get it in mainwid ::draw_sequences_on_pixmap().

Before we fix this issue, we need to load a file that works, to see why it does not fail for most files. We will put a breakpoint at the top mainwid::draw_sequences_on_pixmap().

We hit the breakpoint before even loading a file, with a sequence_count() of 0. The call to valid_sequence(0) passes the test. We may want to make valid_sequence() take the sequence_count() into account. But the call to perf().is_active(0) prevents anything bad from happening at startup time.

Once we load a good file, the sequence_count() is 14 in mainwid::draw_sequences_on_pixmap(). We turn on the display of "offset" using the command "display offset", and "c" (for "continue") until offset = 14, which means we are beyond that last sequence. That bad access is prevented by perf().is active(14).

So the fundamental problem is that perf().is_active(4) is not protecting the access when we load the "bad file". We need to find and fix that issue before papering over the problem with better access checks.

Start again, putting a breakpoint in the call to "new sequence(m_ppqn)" in midifile. This call sets up some members and clears the list of 256 playing notes. Add another breakpoint at "a_perf.add_sequence()" to see what's happening there.

What we find is that the first two tracks have proper sequence numbers as read from the MIDI file, 0 and 1. But the third one preserves the number from the old file, 4. We have a disjunction between the track number and the sequence number, a conceptual problem. We can leave it as is, and beef up the error-checking, or replace the sequence number with the track number when loading the file. What to do?

- Make sure that the is-active flag for all sequences is "false", that the pointers are always null, and make sure to test both of these items (depending on context) before doing anything with the sequence.
- Convert the sequence number to the track number upon saving the MIDI file, or upon reading the MIDI file, and use that number when adding the sequence to the perform object. This might affect some seq24/sequencer64 functionality, however. It's big move.

We need information on reading and importing.

First, if we look at a file that we created long ago by importing b4uacuse.mid, b4uacuse-GM-format. \leftarrow midi, it has its fourteen sequence numbers identical to their track numbers. No problem.

Second, if we just read b4uacuse.mid, a non-seq24-created MIDI file, we see that each of its tracks have no sequence number – they are all zero. The perform::add_sequence() simple iterates from the beginning of m_seqs[] until it finds an inactive m_seqs[i], and uses that element to hold the sequence pointer.

But now it also segfaults! Let's fix all the non-checked get_sequence() calls right away, it is too big an issue to ignore.

In the end, we have to be aware that a screen-set can have blank (null) slots interspersed amongst the active slots.

Licenses

Library This application and its libraries, sub-applications, and documents.

Author(s) Chris Ahlstrom 2015-09-10

5.1 License Terms for the This Project.

Wherever the tag \$XPC_SUITE_GPL_LICENSE\$ appears, or wherever reference to the GPL licensing scheme (any version) is mentioned, substitute the appropriate license text, depending on whether the project is a library, application, documentation, or server software. We're not going to include paragraphs of licensing information in every module; you are responsible for coming here to read the licensing information.

These licenses apply to each sub-project and file artifact in the project with which this license description was packaged.

Wherever the term **XPC** is encountered in this project, it refers to my projects, which go beyond the package that contains this document.

5.2 XPC Application License

The **XPC** application license is either the **GNU GPLv2**. or the **GNU GPLv3**. Generally, projects that originate with me use the latter language, while projects I have extended may specify the former license.

Copyright (C) 2015-2015 by Chris Ahlstrom

This program is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; either version 3 of the License, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the

```
Free Software Foundation, Inc. 51 Franklin Street, Fifth Floor Boston, MA 02110-1301, USA.
```

The text of the GNU GPL version 3 license can also be found here:

```
http://www.gnu.org/licenses/gpl-3.0.txt
```

26 Licenses

5.3 XPC Library License

The XPC library license is the GNU LGPLv3.

Copyright (C) 2015-2015 by Chris Ahlstrom

This library is free software; you can redistribute it and/or modify it under the terms of the GNU Lesser General Public License as published by the Free Software Foundation; either version 3 of the License, or (at your option) any later version.

This library is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Lesser Public License for more details.

You should have received a copy of the GNU Lesser General Public License along with this library; if not, write to

```
Free Software Foundation, Inc. 51 Franklin Street, Fifth Floor Boston, MA 02110-1301, USA.
```

The text of the GNU LGPL version 3 license can also be found here:

```
http://www.gnu.org/licenses/lgpl-3.0.txt
```

5.4 XPC Documentation License

The XPC documentation license is the GNU FDLv1.3.

Copyright (C) 2015-2015 by Chris Ahlstrom

This documentation is free documentation; you can redistribute it and/or modify it under the terms of the GNU Free Documentation License as published by the Free Software Foundation; either version 1.3 of the License, or (at your option) any later version.

This documentation is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Free Documentation License for more details.

You should have received a copy of the GNU Free Documentation License along with this documentation; if not, write to the

```
Free Software Foundation, Inc. 51 Franklin Street, Fifth Floor Boston, MA 02110-1301, USA.
```

The text of the GNU FDL version 1.3 license can also be found here:

```
http://www.gnu.org/licenses/fdl.txt
```

5.5 XPC Affero License 27

5.5 XPC Affero License

The XPC "Affero" license is the GNU AGPLv3.

Copyright (C) 2015-2015 by Chris Ahlstrom

This server software is free server software; you can redistribute it and/or modify it under the terms of the GNU Affero General Public License as published by the Free Software Foundation; either version 1.3 of the License, or (at your option) any later version.

This documentation is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU Free Documentation License for more details.

You should have received a copy of the GNU Affero General Public License along with this server software; if not, write to the

```
Free Software Foundation, Inc. 51 Franklin Street, Fifth Floor Boston, MA 02110-1301, USA.
```

The text of the GNU AGPL version 3 license can also be found here:

```
http://www.gnu.org/licenses/agpl-3.0.txt
```

At the present time, no XPC project uses the "Affero" license.

5.6 XPC License Summary

Include one of these licenses in your Doxygen documentation with one of the following Doxygen tags specified above:

```
\ref gpl_license_subproject
\ref gpl_license_application
\ref gpl_license_library
\ref gpl_license_documentation
\ref gpl_license_affero
```

For more information on navigating GNU licensing, see this page:

```
http://www.gnu.org/licenses/
```

Copies of these licenses (and some logos) are provided in the licenses directory of the main project (or you can search for them at *gnu.org*).

28 Licenses

Todo List

File calculations.cpp

There are additional user-interface and MIDI scaling variables in the perfroll module that we need to move here.

File perfnames.cpp

When bringing up this dialog, and starting play from it, some extra horizontal lines are drawn for some of the sequences. This happens even in seq24, so this is long standing behavior. Is it useful, and how? Where is it done? In perfroll?

Global seg64::editable events::save events ()

Consider what to do about the sequence::m is modified flag.

Global seq64::eventedit::handle_save ()

Could also support writing the events to a new sequence, for added flexibility.

Global seq64::mainwid::timeout ()

We should use this callback to display the current time in the playback.

Global seq64::mainwnd::mainwnd (perform &p, bool allowperf2=true, int ppqn=SEQ64_USE_DEFAULT_← PPQN)

Offload most of the work into an initialization function like options does; make the perform parameter a reference; valgrind flags m_tooltips as lost data, but if we try to manage it ourselves, many more leaks occur.

Global seq64::mainwnd::on_key_release_event (GdkEventKey *ev)

Test this functionality in old and new application.

Global seq64::perfedit::perfedit (perform &p, bool second_perfedit=false, int ppqn=SEQ64_USE_DEFAU← LT_PPQN)

Offload most of the work into an initialization function like options does.

Global seq64::perform::add_sequence (sequence *seq, int perf)

Shouldn't we wrap around the sequence list if we can't find an empty sequence slot after prefnum?

This function needs some deeper analysis against the original, in my opinion.

Global seq64::perform::m_seqs [c_max_sequence]

First, make the sequence array a vector, and second, put allof these flags into a structure and access those members indirectly.

Global seq64::perform::pop_trigger_undo()

Look at seq32/src/perform.cpp and the perform :: push_trigger_undo(track) function, which has a track parameter that has a -1 values the supports all tracks. It requires two new vectors (one for undo, one for redo), two new flags (likewise). We've put this code in place, no longer macroed out, now permanent.

Global seq64::perform::set_left_tick (midipulse tick, bool setstart=true)

The perform::m_one_measure member is currently hardwired to PPQN * 4.

30 Todo List

Global seq64::perfroll::set_ppqn (int ppqn)

Resolve the issue of c_perf_scale_x versus m_perf_scale_x in perfroll.

Global seg64::perftime::set ppqn (int ppqn)

We need make the 4 constant variable per the number of beats (quarter-notes) per bar, and also at least make 16 (4x4) a meaningful manifest constant.

Global seq64::pulses to string (midipulse p)

Still needs to be unit tested.

Global seq64::pulses_to_timestring (midipulse p, const midi_timing &timinginfo)

Still needs to be unit tested.

Global seq64::seqdata::on_scroll_event (GdkEventScroll *ev)

DOCUMENT the segdata scrolling behavior in the documentation projects.

Global seq64::seqedit::get_measures ()

Create a sequence::set units() function or a sequence::get measures() function to forward to.

Global seq64::seqedit::seqedit (perform &perf, sequence &seq, int pos, int ppqn=SEQ64_USE_DEFAULT → PPQN)

Offload most of the work into an initialization function like options does.

Support the hightlight feature in one or both perfedit windows in the same way it is done in the mainwid.

Global seg64::segmenu::m modified

We need to make sure that the perform object is in control of the modification flag.

Global seq64::seqmenu::seq_copy ()

Can be offloaded to a perform member function that accepts a sequence clipboard non-const reference parameter.

Global seq64::seqmenu::seq_cut ()

A lot of seq_cut() can be offloaded to a (new) perform member function that takes a sequence clipboard nonconst reference parameter.

Global seq64::segmenu::seg paste ()

All of seq_paste() can be offloaded to a (new) perform member function with a const clipboard reference parameter.

Global seq64::seqtime::update_pixmap ()

Sizing needs to be controlled by font parameters. Instead of 19 or 20, estimate the width of 3 letters. Instead of 9 pixels down, use the height of the seqtime and the height of a character.

Global seq64::sequence::get_minmax_note_events (int &lowest, int &highest)

For efficency, we should calculate this only when the event set changes, and save the results and return them if good.

Global seq64::sequence::stream event (event &ev)

When we feel like debugging, we will replace the global is-playing call with the parent perform's is-running call.

Global seq64::triggers::next (midipulse *tick_on, midipulse *tick_off, bool *selected, midipulse *tick_← offset)

It would be a bit simpler to simply return a trigger object, wouldn't it?

Deprecated List

Global seq64::clock_tick_duration_bogus (int bpm, int ppqn)

This is a somewhat bogus calculation used only for "statistical" output in the old perform module. Name changed to reflect this unfortunate fact. Use pulse_length_us() instead.

Global seq64::sequence::get_name () const

32 Deprecated List

Namespace Index

8.1 Namespace List

Here is a list of all namespaces with brief descriptions:

Gtk .		4
seq64		
	Define this macro to use the new seg24 v	4

34 Namespace Index

Hierarchical Index

9.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

seq64::AbstractPerfInput
seq64::FruityPerfInput
seq64::Seq24PerfInput
seq64::automutex
seq64::click
seq64::configfile
seq64::optionsfile
seq64::userfile
Dialog
seq64::options
DrawingArea
seq64::gui_palette_gtk2
seq64::gui_drawingarea_gtk2
seg64::eventslots
seq64::maintime
seq64::mainwid
seq64::perfnames
seq64::perfroll
seq64::perftime
seq64::seqdata
seq64::seqevent
seq64::seqkeys
seq64::seqroll
seq64::seqtime
seq64::editable_events
Entry
seq64::keybindentry
seq64::event
seq64::editable_event
seq64::event_list::event_key
seq64::event_list
seq64::font
seq64::FruitySeqEventInput
seq64::FruitySeqRollInput

36 Hierarchical Index

seq64::gui_assistant
seq64::gui_assistant_gtk2
seq64::jack_assistant
seq64::jack_scratchpad
seq64::jack_status_pair_t
seq64::keys_perform
seq64::keys_perform_gtk230
seq64::keys_perform_transfer
seq64::keystroke
seq64::lash
seq64::mastermidibus
seq64::midi_container
seq64::midi_list
seq64::midi_vector
seq64::midi_control
seq64::midi_measures
seq64::midi_splitter
seq64::midi_timing
seq64::midibus
seq64::midifile
seq64::mutex
seq64::condition_var
seq64::editable_event::name_value_t
ObjectBase
seq64::seqmenu
seq64::mainwid
seq64::mainwid
seq64::perfnames
seq64::perfnames
seq64::perfnames 45° seq64::perform 45° seq64::performcallback 52°
seq64::perfnames 45° seq64::perform 45° seq64::performcallback 52° seq64::mainwnd 33°
seq64::perfnames 45° seq64::perform 45° seq64::performcallback 52° seq64::mainwnd 33° seq64::rc_settings 55°
seq64::perfnames 45 seq64::perform 45 seq64::performcallback 52 seq64::mainwnd 336 seq64::rc_settings 556 seq64::rect 576
seq64::perfnames 45° seq64::perform 45° seq64::performcallback 52° seq64::mainwnd 33° seq64::rc_settings 55° seq64::rect 57° seq64::gui_drawingarea_gtk2::rect 57°
seq64::perfnames 45 seq64::perform 45 seq64::performcallback 52 seq64::mainwnd 33 seq64::rc_settings 55 seq64::rect 57 seq64::gui_drawingarea_gtk2::rect 57 seq64::Seq24SeqEventInput 58
seq64::perfnames 45 seq64::perform 45 seq64::performcallback 52 seq64::mainwnd 33 seq64::rc_settings 55 seq64::rect 57 seq64::gui_drawingarea_gtk2::rect 57 seq64::Seq24SeqEventInput 580 seq64::sequence 680
seq64::perfnames 45 seq64::perform 45 seq64::performcallback 52 seq64::mainwnd 336 seq64::rc_settings 55 seq64::rect 576 seq64::gui_drawingarea_gtk2::rect 576 seq64::Seq24SeqEventInput 580 seq64::sequence 689 seq64::trigger 752
seq64::perform 45 seq64::performcallback 526 seq64::mainwnd 336 seq64::rc_settings 556 seq64::rect 576 seq64::gui_drawingarea_gtk2::rect 576 seq64::Seq24SeqEventInput 580 seq64::trigger 752 seq64::triggers 756
seq64::perform 45 seq64::performcallback 526 seq64::mainwnd 336 seq64::rc_settings 556 seq64::rect 576 seq64::gui_drawingarea_gtk2::rect 576 seq64::Seq24SeqEventInput 580 seq64::trigger 752 seq64::triggers 756
seq64::perform 455 seq64::performcallback 526 seq64::mainwnd 336 seq64::rc_settings 556 seq64::rect 576 seq64::gui_drawingarea_gtk2::rect 576 seq64::Seq24SeqEventInput 580 seq64::sequence 680 seq64::trigger 756 seq64::triggers 756 seq64::user_instrument 776
seq64::perform 455 seq64::performcallback 526 seq64::mainwnd 336 seq64::rc_settings 556 seq64::rect 576 seq64::gui_drawingarea_gtk2::rect 576 seq64::Seq24SeqEventInput 580 seq64::sequence 688 seq64::trigger 756 seq64::user_instrument 777 seq64::user_instrument_t 776
seq64::perform 455 seq64::performcallback 526 seq64::mainwnd 336 seq64::rc_settings 556 seq64::rect 575 seq64::gui_drawingarea_gtk2::rect 576 seq64::Seq24SeqEventInput 586 seq64::sequence 688 seq64::trigger 756 seq64::user_instrument 776 seq64::user_instrument_t 776 seq64::user_midi_bus 777
seq64::perform 45 seq64::performcallback 52 seq64::performcallback 52 seq64::rend 336 seq64::rect seq64::rect 576 seq64::gui_drawingarea_gtk2::rect 576 seq64::Seq24SeqEventInput 580 seq64::sequence 686 seq64::trigger 756 seq64::triggers 756 seq64::user_instrument 777 seq64::user_instrument_t 776 seq64::user_midi_bus 777 seq64::user_midi_bus_t 78
seq64::perform 45 seq64::performcallback 52 seq64::mainwnd 336 seq64::rc_settings 55 seq64::rect 57 seq64::gui_drawingarea_gtk2::rect 57 seq64::Seq24SeqEventInput 58 seq64::sequence 68 seq64::trigger 75 seq64::user_instrument 77 seq64::user_instrument_t 77 seq64::user_midi_bus 77 seq64::user_midi_bus_t 78 seq64::user_settings 78
seq64::perfnames 45 seq64::perform 45 seq64::performcallback 52 seq64::mainwnd 33 seq64::rc_settings 55 seq64::rect 57 seq64::gui_drawingarea_gtk2::rect 57 seq64::Seq24SeqEventInput 58 seq64::sequence 68 seq64::rigger 75 seq64::triggers 75 seq64::user_instrument 77 seq64::user_instrument_t 77 seq64::user_midi_bus 77 seq64::user_midi_bus_t 78 seq64::user_settings 78 Window Window
seq64::perform 45 seq64::performcallback 526 seq64::mainwnd 336 seq64::rc_settings 556 seq64::rect 576 seq64::gui_drawingarea_gtk2::rect 576 seq64::Seq24SeqEventInput 580 seq64::sequence 680 seq64::trigger 756 seq64::user_instrument 777 seq64::user_instrument_t 777 seq64::user_midi_bus 777 seq64::user_midi_bus_t 78 seq64::user_settings 78 Window seq64::gui_window_gtk2 244
seq64::perform 45 seq64::perform 45 seq64::performcallback 52 seq64::mainwnd 33 seq64::rc_settings 55 seq64::rect 57 seq64::gui_drawingarea_gtk2::rect 57 seq64::seq24SeqEventInput 58 seq64::sequence 68 seq64::trigger 75 seq64::user_instrument 77 seq64::user_instrument_t 77 seq64::user_midi_bus 77 seq64::user_midi_bus_t 78 seq64::user_settings 78 Window 58 seq64::gui_window_gtk2 24 seq64::eventedit 166
seq64::perfnames 45 seq64::perform 45 seq64::performcallback 52 seq64::mainwnd 33 seq64::rc_settings 556 seq64::rect 57 seq64::gui_drawingarea_gtk2::rect 57 seq64::seq24SeqEventlnput 58 seq64::sequence 68 seq64::rigger 75 seq64::triggers 75 seq64::user_instrument 77 seq64::user_instrument_t 77 seq64::user_midi_bus 77 seq64::user_midi_bus_t 78 seq64::user_settings 78 Window seq64::gui_window_gtk2 24 seq64::eventedit 166 seq64::lfownd 314

Data Structure Index

10.1 Data Structures

Here are the data structures with brief descriptions:

seq64::AbstractPerfinput	
Provides an abstract base class to provide the minimal interface for the various "perf input"	
classes	101
seq64::automutex	
Provides a mutex that locks automatically when created, and unlocks when destroyed	104
seq64::click	
Encapsulates any possible mouse click	106
seq64::condition_var	
A mutex works best in conjunction with a condition variable	110
seq64::configfile	
This class is the abstract base class for optionsfile and userfile	112
seq64::editable_event	
Provides for the management of MIDI editable events	115
seq64::editable_events	
Provides for the management of an ordered collection MIDI editable events	128
seq64::event	400
Provides events for management of MIDI events	136
seq64::event_list::event_key	15/
Provides a key value for an event map	154
seq64::event_list Receptable for MIDI events	155
seq64::eventedit	150
This class supports an Event Editor that is used to tweak the details of events and get a better	
idea of the mix of events in a sequence	166
seq64::eventslots	
This class implements the left-side list of events in the pattern event-edit window	180
seq64::font	
This class provides a wrapper for rendering fonts that are encoded as a 16 x 16 pixmap file in	
XPM format	197
seq64::FruityPerfInput	
Implements the performance input of that certain fruity sequencer that people seem to like	202
seq64::FruitySeqEventInput	
This structure implements the interaction methods for the "fruity" mode of operation	206
seq64::FruitySeqRollInput	
Implements the fruity mouse interaction paradigm for the segroll	209

38 Data Structure Index

seq64::gui_assistant	
This class provides an interface for some of the GUI support needed in Sequencer64	212
seq64::gui_assistant_gtk2 This class provides an interface for some of the Gtk/Gdk/Glib support needed in Sequencer64	214
seq64::gui_drawingarea_gtk2	
Implements the basic drawing areas of the application	216
Implements a stock palette of Gdk::Color elements	234
seq64::gui window gtk2	
This class supports a basic interface for Gtk::Window-derived objects	244
seq64::jack_assistant This class provides the performance mode JACK support	248
seq64::jack_scratchpad	
Provide a temporary structure for passing data and results between a perform and jack_assistant object	268
seq64::jack_status_pair_t	
Provides an internal type to make it easier to display a specific and accurate human-readable	
message when a JACK operation fails	270
seq64::keybindentry Class for management of application key-bindings	271
seq64::keys_perform	
This class supports the performance mode	274
	201
This class supports the performance mode	301
seq64::keys_perform_transfer Provides a data-transfer structure to make it easier to fill in a keys_perform object's members using sscanf()	303
seq64::keystroke	
Encapsulates any practical keystroke	306
seq64::lash	
This class supports LASH operations, if compiled with LASH support (i.e seq64::Ifownd	311
One LFO window class	314
seq64::maintime	
This class provides the drawing of the progress bar at the top of the main window, along with two "pills" that move in time with the beat and measure	317
seq64::mainwid	
This class implements the piano roll area of the application seq64::mainwnd	323
This class implements the functionality of the main window of the application, except for the	
Patterns Panel functionality, which is implemented in the mainwid class	336
seq64::mastermidibus	
The class that "supervises" all of the midibus objects?	353
seq64::midi_container	
This class is the abstract base class for a container of MIDI track information	367
seq64::midi_control	
This class (formerly a struct) contains the control information for sequences that make up a live	
set	374
seq64::midi_list	
This class is the std::list implementation of the midi_container	378
seq64::midi_measures	
Provides a data structure to hold the numeric equivalent of the measures string "measures :beats:divisions" ("m:b:d")	382
seq64::midi_splitter	302
This class handles the parsing and writing of MIDI files	384
seq64::midi_timing	
We anticipate the need to have a small structure holding the parameters needed to calculate MIDI times within an arbitrary song	388

10.1 Data Structures 39

seq64::midi_vector	
This class is the std::vector implementation of the midi_container	392
seq64::midibus Provides a class for handling the MIDI buss on Linux	395
seq64::midifile	
This class handles the parsing and writing of MIDI files	403
seq64::mutex	
Simple wrapper for the pthread_mutex_t type used as a recursive mutex	423
seq64::editable_event::name_value_t	
Provides a type that contains the pair of values needed for the various lookup maps that are	
needed to manage editable events	424
seq64::options	
This class supports a full tabbed options dialog	425
seq64::optionsfile	
Provides a file for reading and writing the application' main configuration file	430
seq64::perfedit	
This class supports a Performance Editor that is used to arrange the patterns/sequences defined	
in the patterns panel	434
seq64::perfnames	
This class implements the left-side keyboard in the patterns window	451
seq64::perform	
This class supports the performance mode	459
seq64::performcallback	500
Provides for notification of events	529
seq64::perfroll	-
This class implements the performance roll user interface	530
seq64::perftime	
This class implements drawing the piano time at the top of the "performance window" (the "song	E 40
editor")	549
seq64::rc_settings This class centains the entires formerly named "global yyyyyy"	EEC
This class contains the options formerly named "global_xxxxxxx"	558
Seq64::rect A small helper class representing a rectangle	E75
seq64::gui drawingarea gtk2::rect	575
A small helper structure representing a rectangle	E76
· · · · · · · · · · · · · · · · · · ·	576
seq64::Seq24PerfInput Implements the default (Seq24) performance input characteristics of this application	577
	377
seq64::Seq24SeqEventInput This structure implement the normal interaction methods for Seq24	E00
	580
Seq64::seqdata This close supports drawing pione rell evention on a window	582
This class supports drawing piano-roll eventis on a window	302
seq64::seqedit Implements the Pattern Editor, which has references to:	593
·	595
Seq64::seqevent Implements the piano event drawing area	622
seq64::seqkeys	022
This class implements the left side piano of the pattern/sequence editor	636
seq64::seqmenu	030
This class handles the right-click menu of the sequence slots in the pattern window	646
- · · · · · · · · · · · · · · · · · · ·	040
seq64::seqroll Implements the piano roll section of the pattern editor	655
seq64::seqtime	000
This class implements the piano time, whatever that is	684
seq64::sequence	JU4
Firstly a receptable for a single track of MIDI data read from a MIDI file or edited into a pattern	689
seq64::trigger	003
This class hold a single trigger for a sequence object	752
This stass from a single trigger for a sequence object	1 32

40 Data Structure Index

seq64::triggers	
Receptable the triggers that can be used with a sequence object	756
seq64::user_instrument	
Provides data about the MIDI instruments, readable from the "user" configuration file	772
seq64::user_instrument_t	
This structure corresponds to [user-instrument-N] definitions in the \sim /.seq24usr	
or ~/.config/sequencer64/sequencer64.usr file	776
seq64::user_midi_bus	
Provides data about the MIDI busses, readable from the "user" configuration file	777
seq64::user_midi_bus_t	
This structure corresponds to [user-midi-bus-0] definitions in the \sim /.seq24usr	
("user") file (\sim /.config/sequencer64/sequencer64.usr in the latest version of the	
application)	781
seq64::user_settings	
Holds the current values of sequence settings and settings that can modify the number of se-	
quences and the configuration of the user-interface	781
seq64::userfile	
Supports the user's \sim /.config/sequencer64/sequencer64.usr and \sim /.seq24us	sr
configuration file	811

Namespace Documentation

11.1 Gtk Namespace Reference

11.2 seq64 Namespace Reference

Define this macro to use the new seq24 v.

Data Structures

class AbstractPerfInput

Provides an abstract base class to provide the minimal interface for the various "perf input" classes.

· class automutex

Provides a mutex that locks automatically when created, and unlocks when destroyed.

· class click

Encapsulates any possible mouse click.

· class condition_var

A mutex works best in conjunction with a condition variable.

· class configfile

This class is the abstract base class for optionsfile and userfile.

class editable_event

Provides for the management of MIDI editable events.

class editable_events

Provides for the management of an ordered collection MIDI editable events.

· class event

Provides events for management of MIDI events.

· class event_list

The event_list class is a receptable for MIDI events.

· class eventedit

This class supports an Event Editor that is used to tweak the details of events and get a better idea of the mix of events in a sequence.

· class eventslots

This class implements the left-side list of events in the pattern event-edit window.

class font

This class provides a wrapper for rendering fonts that are encoded as a 16 x 16 pixmap file in XPM format.

class FruityPerfInput

Implements the performance input of that certain fruity sequencer that people seem to like.

struct FruitySeqEventInput

This structure implements the interaction methods for the "fruity" mode of operation.

class FruitySeqRollInput

Implements the fruity mouse interaction paradigm for the seqroll.

· class gui assistant

This class provides an interface for some of the GUI support needed in Sequencer64.

class gui_assistant_gtk2

This class provides an interface for some of the Gtk/Gdk/Glib support needed in Sequencer64.

class gui_drawingarea_gtk2

Implements the basic drawing areas of the application.

· class gui_palette_gtk2

Implements a stock palette of Gdk::Color elements.

· class gui_window_gtk2

This class supports a basic interface for Gtk::Window-derived objects.

· class jack assistant

This class provides the performance mode JACK support.

class jack_scratchpad

Provide a temporary structure for passing data and results between a perform and jack_assistant object.

· struct jack status pair t

Provides an internal type to make it easier to display a specific and accurate human-readable message when a JACK operation fails.

class keybindentry

Class for management of application key-bindings.

class keys_perform

This class supports the performance mode.

class keys_perform_gtk2

This class supports the performance mode.

struct keys_perform_transfer

Provides a data-transfer structure to make it easier to fill in a keys perform object's members using sscanf().

· class keystroke

Encapsulates any practical keystroke.

class lash

This class supports LASH operations, if compiled with LASH support (i.e.

· class Ifownd

One LFO window class.

class maintime

This class provides the drawing of the progress bar at the top of the main window, along with two "pills" that move in time with the beat and measure.

· class mainwid

This class implements the piano roll area of the application.

· class mainwnd

This class implements the functionality of the main window of the application, except for the Patterns Panel functionality, which is implemented in the mainwid class.

· class mastermidibus

The class that "supervises" all of the midibus objects?

class midi_container

This class is the abstract base class for a container of MIDI track information.

· class midi control

This class (formerly a struct) contains the control information for sequences that make up a live set.

· class midi_list

This class is the std::list implementation of the midi_container.

· class midi measures

Provides a data structure to hold the numeric equivalent of the measures string "measures:beats:divisions" ("m:b:d").

class midi_splitter

This class handles the parsing and writing of MIDI files.

· class midi_timing

We anticipate the need to have a small structure holding the parameters needed to calculate MIDI times within an arbitrary song.

· class midi_vector

This class is the std::vector implementation of the midi_container.

· class midibus

Provides a class for handling the MIDI buss on Linux.

· class midifile

This class handles the parsing and writing of MIDI files.

· class mutex

The mutex class provides a simple wrapper for the pthread_mutex_t type used as a recursive mutex.

· class options

This class supports a full tabbed options dialog.

· class optionsfile

Provides a file for reading and writing the application' main configuration file.

· class perfedit

This class supports a Performance Editor that is used to arrange the patterns/sequences defined in the patterns panel.

class perfnames

This class implements the left-side keyboard in the patterns window.

· class perform

This class supports the performance mode.

· struct performcallback

Provides for notification of events.

· class perfroll

This class implements the performance roll user interface.

· class perftime

This class implements drawing the piano time at the top of the "performance window" (the "song editor").

class rc_settings

This class contains the options formerly named "global_xxxxxx".

· class rect

A small helper class representing a rectangle.

class Seq24PerfInput

 ${\it Implements the default (Seq 24) performance input characteristics of this application.}$

• struct Seq24SeqEventInput

This structure implement the normal interaction methods for Seq24.

· class seqdata

This class supports drawing piano-roll eventis on a window.

· class segedit

Implements the Pattern Editor, which has references to:

· class seqevent

Implements the piano event drawing area.

· class segkeys

This class implements the left side piano of the pattern/sequence editor.

class segmenu

This class handles the right-click menu of the sequence slots in the pattern window.

class segroll

Implements the piano roll section of the pattern editor.

· class segtime

This class implements the piano time, whatever that is.

· class sequence

The sequence class is firstly a receptable for a single track of MIDI data read from a MIDI file or edited into a pattern.

· class trigger

This class hold a single trigger for a sequence object.

· class triggers

The triggers class is a receptable the triggers that can be used with a sequence object.

· class user instrument

Provides data about the MIDI instruments, readable from the "user" configuration file.

· struct user instrument t

This structure corresponds to [user-instrument-N] definitions in the \sim /.seq24usr or \sim /.config/sequencer64/sequencer file.

· class user midi bus

Provides data about the MIDI busses, readable from the "user" configuration file.

· struct user midi bus t

This structure corresponds to [user-midi-bus-0] definitions in the \sim /.seq24usr ("user") file (\sim /.config/sequencer64/sequencer64.usr in the latest version of the application).

· class user settings

Holds the current values of sequence settings and settings that can modify the number of sequences and the configuration of the user-interface.

· class userfile

Supports the user's \sim /.config/sequencer64/sequencer64.usr and \sim /.seq24usr configuration file.

Typedefs

· typedef unsigned char midibyte

Provides a fairly common type definition for a byte value.

· typedef unsigned char bussbyte

Distinguishes a buss/bus number from other MIDI bytes.

· typedef unsigned short midishort

Distinguishes a short value from the unsigned short values implicit in short-valued MIDI numbers.

typedef unsigned long midilong

Distinguishes a long value from the unsigned long values implicit in long-valued MIDI numbers.

· typedef long midipulse

Distinguishes a long value from the unsigned long values implicit in MIDI time measurements.

Enumerations

```
    enum wave_type_t {
        WAVE_NONE,
        WAVE_SINE,
        WAVE_TRIANGLE,
        WAVE_INVERSE_TRIANGLE,
        WAVE STEP }
```

Provides a clear enumation of wave types supported by the wave function.

```
enum seq_modifier_t {
 SEQ64 NO MASK,
 SEQ64_SHIFT_MASK,
 SEQ64_LOCK_MASK,
 SEQ64_CONTROL_MASK,
 SEQ64 MOD1 MASK,
 SEQ64 MOD2 MASK,
 SEQ64 MOD3 MASK,
 SEQ64 MOD4 MASK,
 SEQ64 MOD5 MASK,
 SEQ64_BUTTON1_MASK,
 SEQ64_BUTTON2_MASK,
 SEQ64_BUTTON3_MASK,
 SEQ64 BUTTON4 MASK,
 SEQ64_BUTTON5_MASK,
 SEQ64_SUPER_MASK,
 SEQ64 HYPER MASK,
 SEQ64 META MASK,
 SEQ64_RELEASE_MASK,
 SEQ64_MASK_MAX }
     Types of modifiers, essentially copied from gtk-2.0/gdk/gdktypes.h.
• enum seq_event_type_t {
 SEQ64_NOTHING,
 SEQ64 DELETE,
 SEQ64 DESTROY.
 SEQ64_EXPOSE,
 SEQ64 MOTION NOTIFY,
 SEQ64 BUTTON PRESS,
 SEQ64_2BUTTON_PRESS,
 SEQ64_3BUTTON_PRESS,
 SEQ64 BUTTON RELEASE,
 SEQ64_KEY_PRESS,
 SEQ64_KEY_RELEASE,
 SEQ64 SCROLL,
 SEQ64 EVENT LAST }
    Event types copped from gtk-2.0/gdk/gdkevents.h for use with this application.

    enum seg scroll direction t {

 SEQ64_SCROLL_UP,
 SEQ64_SCROLL_DOWN,
 SEQ64_SCROLL_LEFT,
 SEQ64 SCROLL RIGHT }
     Types of scroll events, essentially copied from gtk-2.0/gdk/gdkevents.h.
• enum clock e {
 e_clock_off,
 e_clock_pos,
 e_clock_mod }
    A clock enumeration, as used in the File / Options / MIDI Clock dialog.

    enum interaction method t {

 e_seq24_interaction,
 e_fruity_interaction,
 e_number_of_interactions }
    Provides codes for the mouse-handling used by the application.
enum c_music_scales {
 c scale off,
 c scale major,
 c_scale_minor,
 c_scale_harmonic_minor,
```

```
c_scale_melodic_minor,
  c scale c whole tone,
  c_scale_blues,
  c_scale_major_pentatonic,
  c_scale_minor_pentatonic,
  c scale size }
     Corresponds to the small number of musical scales that the application can handle.
enum draw_type_t {
  DRAW FIN,
  DRAW_NORMAL_LINKED,
  DRAW_NOTE_ON,
  DRAW NOTE OFF }
     Provides a set of methods for drawing certain items.
• enum mouse action e {
  e_action_select,
  e_action_draw,
  e_action_grow }
     Mouse actions, for the Pattern Editor.
enum edit action t {
  c select all notes,
  c select all events,
  c_select_inverse_notes,
  c_select_inverse_events,
  c quantize notes,
  c_quantize_events,
  c_tighten_events,
  c tighten notes,
  c transpose notes,
  c reserved,
  c_transpose_h,
  c_expand_pattern,
  c compress pattern,
  c_select_even_notes,
  c_select_odd_notes,
  c_swing_notes }
     Actions.
```

Functions

bool extract_timing_numbers (const std::string &s, std::string &part_1, std::string &part_2, std::string &part ← __3, std::string &fraction)

Extracts up to 4 numbers from a colon-delimited string.

std::string pulses_to_string (midipulse p)

Converts MIDI pulses (also known as ticks, clocks, or divisions) into a string.

std::string pulses_to_measurestring (midipulse p, const midi_timing &seqparms)

Converts a MIDI pulse/ticks/clock value into a string that represents "measures:beats:ticks" ("measures:beats⇔:division").

bool pulses to midi measures (midipulse p, const midi timing &segparms, midi measures &measures)

Converts a MIDI pulse/ticks/clock value into a string that represents "measures:beats:ticks" ("measures:beats⇔:division").

std::string pulses_to_timestring (midipulse p, int bpm, int ppqn)

Converts a MIDI pulse/ticks/clock value into a string that represents "hours:minutes:seconds.fraction".

• std::string pulses_to_timestring (midipulse p, const midi_timing &timinginfo)

Converts a MIDI pulse/ticks/clock value into a string that represents "hours:minutes:seconds.fraction".

• midipulse measurestring_to_pulses (const std::string &measures, const midi_timing &seqparms)

Converts a string that represents "measures:beats:division" to a MIDI pulse/ticks/clock value.

midipulse midi measures to pulses (const midi measures &measures, const midi timing &seqparms)

Converts a string that represents "measures:beats:division" to a MIDI pulse/ticks/clock value.

midipulse timestring to pulses (const std::string ×tring, int bpm, int ppqn)

Converts a string that represents "hours:minutes:seconds.fraction" into a MIDI pulse/ticks/clock value.

midipulse string to pulses (const std::string &s, const midi timing &mt)

Converts a time string to pulses.

• midibyte string_to_midibyte (const std::string &s)

Converts a string to a MIDI byte.

std::string shorten_file_spec (const std::string &fpath, int leng)

Shortens a file-specification to make sure it is no longer than the provided length value.

bool string_not_void (const std::string &s)

Tests that a string is not empty and has non-space characters.

• bool string_is_void (const std::string &s)

Tests that a string is empty or has only white-space characters.

bool strings_match (const std::string &target, const std::string &x)

Compares two strings for a form of semantic equality, for the purposes of editable_event(), for example.

int log2_time_sig_value (int tsd)

Calculates the log-base-2 value of a number that is already a power of 2.

void tempo_us_to_bytes (midibyte t[3], int tempo_us)

Provide a way to convert a tempo value (microseconds per quarter note) into the three bytes needed as value in a Tempo meta event.

int zoom power of 2 (int ppqn)

Calculates a suitable starting zoom value for the given PPQN value.

• double beats_per_minute_from_tempo_us (double tempous)

This function calculates the effective beats-per-minute based on the value of a Tempo meta-event.

double tempo_us_from_beats_per_minute (double bpm)

This function is the inverse of beats_per_minute_from_tempo().

long tempo_to_us (int bpm)

Converts tempo (e.g.

double pulse length us (int bpm, int ppqn)

Calculates pulse-length from the BPM (beats-per-minute) and PPQN (pulses-per-quarter-note) values.

double delta_time_us_to_ticks (unsigned long us, int bpm, int ppqn)

Converts delta time in microseconds to ticks.

• double ticks_to_delta_time_us (midipulse delta_ticks, int bpm, int ppqn)

Converts the time in ticks ("clocks") to delta time in microseconds.

double clock_tick_duration_bogus (int bpm, int ppqn)

Calculates the duration of a clock tick based on PPQN and BPM settings.

int clock_ticks_from_ppqn (int ppqn)

A simple calculation to convert PPQN to MIDI clock ticks.

double double_ticks_from_ppqn (int ppqn)

A simple calculation to convert PPQN to MIDI clock ticks.

• midipulse pulses_per_measure (int ppqn=SEQ64_DEFAULT_PPQN)

Calculates the pulses per measure.

• midipulse measures_to_ticks (int bpm, int ppqn, int bw, int measures=1)

Calculates the length of an integral number of measures, in ticks.

double wave_func (double angle, wave_type_t wavetype)

Calculates a wave function for use as an LFO (low-frequency oscillator) for modifying data values in a sequence.

bool help_check (int argc, char *argv [])

Checks to see if the first option is a help or version argument, just so we can skip the "Reading configuration ..." messages.

bool parse_options_files (perform &p, int argc, char *argv [])

Provides the command-line option support, as well as some setup support, extracted from the main routine of Sequencer64.

• int parse_command_line_options (perform &p, int argc, char *argv [])

Parses the command-line options on behalf of the application.

bool write_options_files (const perform &p)

Saves all options to the "rc" and "user" configuration files.

std::string build_details ()

Generates a string describing the features of the build.

• std::string to_string (const event &ev)

A free function to convert an event into an informative string, just enough to save some debugging time.

- bool file_access (const std::string &targetfile, int mode)
- bool file exists (const std::string &filename)

Checks a file for existence.

bool file_readable (const std::string &filename)

Checks a file for readability.

• bool file_writable (const std::string &filename)

Checks a file for writability.

bool file accessible (const std::string &filename)

Checks a file for readability and writability.

bool file_executable (const std::string &filename)

Checks a file for the ability to be executed.

bool file_is_directory (const std::string &filename)

Checks a file to see if it is a directory.

bool make_directory (const std::string &pathname)

A function to ensure that the \sim /.config/sequencer64 directory exists.

bool ppqn is valid (int ppqn)

Common code for handling PPQN settings.

• int jack_sync_callback (jack_transport_state_t state, jack_position_t *pos, void *arg)

Global functions for JACK support and JACK sessions.

void jack_shutdown_callback (void *arg)

This callback is to shut down JACK by clearing the <code>jack_assistant</code> :: <code>m_jack_running</code> flag.

void jack_timebase_callback (jack_transport_state_t state, jack_nframes_t nframes, jack_position_t *pos, int new_pos, void *arg)

The JACK timebase function defined here sets the JACK position structure.

- int jack_process_callback (jack_nframes_t nframes, void *arg)
- long get_current_jack_position (void *arg)
- void jack_session_callback (jack_session_event_t *ev, void *arg)

Set the m_jsession_ev (event) value of the perform object.

- bool invalid_key (unsigned int key)
- std::string keyval_name (unsigned int key)

Obtains the name of the key.

void keyval_normalize (keys_perform_transfer &k)

For the case in which the "rc" file is missing or corrupt, this function makes sure that each control key has a reasonable value.

bool create_lash_driver (perform &p, int argc, char **argv)

Creates and starts a lash object.

• lash * lash driver ()

Provides access to the lash object.

void delete_lash_driver ()

Deletes the last object.

bool is_null_midipulse (midipulse p)

Compares a midipulse value to SEQ64_NULL_MIDIPULSE.

void * output_thread_func (void *p)

Global functions defined in perform.cpp.

void * input thread func (void *myperf)

Set up the performance, and set the process to realtime privileges.

• rc_settings & rc ()

Returns a reference to the global rc_settings object.

user_settings & usr ()

Returns a reference to the global user settings object, for better encapsulation.

int choose_ppqn (int ppqn)

Common code for handling PPQN settings.

• long min (long a, long b)

min() for long values.

• static std::string make_section_name (const std::string &label, int value)

Provides a purely internal, ad hoc helper function to create numbered section names for the userfile class.

font & font_render ()

The p_font_renderer pointer was once created in the main module, sequencer64.cpp.

Gtk::Adjustment & adjustment dummy ()

Provides a way to provide a dummy Gtk::Adjustment object, but not create one until it is actually needed, so that the Glib/Gtk infrastructure is ready for it.

void update_mainwid_sequences ()

This global function in the seq64 namespace calls mainwid :: update_sequences_on_window(), if the global mainwid object exists.

void update_perfedit_sequences ()

This global function in the seq64 namespace calls perfedit :: draw_sequences(), if the global perfedit objects exist.

int FF RW timeout (void *arg)

This global function in the seq64 namespace is passed to the gtk_timeout callback.

static long clamp (long val, long low, long hi)

An internal function used by the FruitySeqRollInput class.

• static long clamp (long val, long low, long hi)

An internal function used by the FruitySeqRollInput class.

Variables

std::string c_controller_names [SEQ64_MIDI_COUNT_MAX]

Provides the default names of MIDI controllers.

· const midibyte EVENT_STATUS_BIT

This highest bit of the status byte is always 1.

const midibyte EVENT_ANY

Channel Voice Messages.

- const midibyte EVENT_NOTE_OFF
- · const midibyte EVENT NOTE ON
- const midibyte EVENT AFTERTOUCH
- const midibyte EVENT_CONTROL_CHANGE
- const midibyte EVENT_PROGRAM_CHANGE
- const midibyte EVENT_CHANNEL_PRESSURE
- const midibyte EVENT_PITCH_WHEEL
- const midibyte EVENT_MIDI_SYSEX

System Messages.

- const midibyte EVENT_MIDI_QUARTER_FRAME
- const midibyte EVENT_MIDI_SONG_POS
- · const midibyte EVENT MIDI SONG SELECT
- · const midibyte EVENT MIDI SONG F4
- · const midibyte EVENT MIDI SONG F5
- const midibyte EVENT_MIDI_TUNE_SELECT
- const midibyte EVENT_MIDI_SYSEX_END
- const midibyte EVENT MIDI SYSEX CONTINUE
- · const midibyte EVENT MIDI CLOCK
- · const midibyte EVENT MIDI SONG F9
- const midibyte EVENT MIDI START
- const midibyte EVENT_MIDI_CONTINUE
- const midibyte EVENT_MIDI_STOP
- const midibyte EVENT_MIDI_SONG_FD
- · const midibyte EVENT MIDI ACTIVE SENS
- const midibyte EVENT MIDI RESET
- const midibyte EVENT_MIDI_META

0xFF is a MIDI "escape code" used in MIDI files to introduce a MIDI meta event.

· const midibyte EVENT NULL CHANNEL

This value of 0xFF is Sequencer64's channel value that indicates that the event's m_channel value is bogus.

const midibyte EVENT_GET_CHAN_MASK

These file masks are used to obtain or to mask off the channel data from a status byte.

- · const midibyte EVENT CLEAR CHAN MASK
- · const int EVENTS ALL

Variable from the "stazed" extras.

- const int EVENTS_UNSELECTED
- const int c_midibus_output_size

Manifest global constants.

const int c_midibus_input_size

The c_midibus_input_size value is passed, in mastermidibus, to snd_seq_set_input_buffer_size().

const int c_midibus_sysex_chunk

Controls the amount a SysEx data sent at one time, in the midibus module.

const midilong c_midibus

Provides tags used by the midifile class to control the reading and writing of the extra "proprietary" information stored in a Seq24 MIDI file.

const midilong c_midich

Track channel number.

const midilong c_midiclocks

Track clocking.

const midilong c_triggers

See c_triggers_new.

• const midilong c_notes

Song data.

const midilong c_timesig

Track time signature.

· const midilong c bpmtag

Song beats/minute.

const midilong c_triggers_new

Track trigger data.

· const midilong c mutegroups

Song mute group data.

const midilong c_midictrl

Song MIDI control.

· const midilong c_musickey

The track's key.

· const midilong c_musicscale

The track's scale.

· const midilong c backsequence

Track background sequence.

· const midilong c transpose

Track transpose value.

const midilong c_perf_bp_mes

Perfedit beats/measure.

const midilong c_perf_bw

Perfedit beat-width.

• const int c_midi_track_ctrl

Pseudo control values for associating MIDI events (I think) with automation of some of the controls in seq24.

- · const int c midi control bpm up
- const int c_midi_control_bpm_dn
- const int c_midi_control_ss_up
- · const int c midi control ss dn
- · const int c midi control mod replace
- · const int c midi control mod snapshot
- const int c_midi_control_mod_queue
- · const int c_midi_control_mod_gmute
- · const int c_midi_control_mod_glearn
- const int c_midi_control_play_ss
- · const int c midi controls
- const bool c_scales_policy [c_scale_size][SEQ64_OCTAVE_SIZE]

Each value in the kind of scale is denoted by a true value in these arrays.

• const int c_scales_transpose_up [c_scale_size][SEQ64_OCTAVE_SIZE]

Increment values needed to transpose each scale up so that it remains in the same key.

• const int c_scales_transpose_dn [c_scale_size][SEQ64_OCTAVE_SIZE]

Making these positive makes it easier to read, but the actual array contains negative values.

• const char c_scales_text [c_scale_size][20]

The names of the currently-supported scales.

const char c_key_text [SEQ64_OCTAVE_SIZE][4]

Provides the entries for the Key dropdown menu in the Pattern Editor window.

• const char c_interval_text [16][4]

Provides the entries for the Interval dropdown menu in the Pattern Editor window.

const char c_chord_text [8][6]

Provides the entries for the Chord dropdown menu in the Pattern Editor window.

const int c_chord_number

Additional support data for the chord-generation feature from Stazed's seq32 project.

const char c_chord_table_text [c_chord_number][12]

Additional support data for the chord-generation feature from Stazed's seq32 project.

· const int c_chord_size

Provides the number of chord values in each chord's specification array.

const int c_chord_table [c_chord_number][c_chord_size]

Additional support data for the chord-generation feature from Stazed's seq32 project.

const int c_max_instruments

Provides the maximum number of instruments that can be defined in the \sim /.seq24usr or \sim /.config/sequencer64/sequencer6.

const int c_max_busses

Provides the maximum number of MIDI buss definitions supported in the "user" file.

static const std::string versiontext

Sets up the "hardwired" version text for Sequencer64.

static struct option long_options []

A structure for command parsing that provides the long forms of command-line arguments, and associates them with their respective short form.

static const std::string s_arg_list

Provides a complete list of the short options, and is passed to getopt_long().

static const char *const s_help_1a

Provides help text.

• static const char *const s help 1b

More help text.

static const char *const s_help_2

Still more help text.

static const char *const s_help_3

Still more help text.

• static const char *const s_help_4

Still more help text.

static const std::string s_build_highlight_empty

This section of variables provide static information about the options enabled or disabled during the build.

- static const std::string s build lash support
- static const std::string s_build_jack_support
- static const std::string s build jack session
- · static const std::string s_event_editor
- static const std::string s build pause support
- static const std::string s build use event map
- · static const std::string s build chord generator
- static const std::string s_build_edit_highlight
- static const std::string s_build_timesig_tempo
- static const std::string s_build_midi_vector
- static const std::string s_build_solid_grid
- static const std::string s_build_follow_progress
- static const std::string s_statistics_support
- static const std::string s_strip_empty_mutes
- static const std::string s_seq32_jack_support
- static const std::string s_seq32_transport
- static const std::string s_seq32_transpose
- static const std::string s_seq32_menu_buttons
- struct charpair_t s_character_mapping []

The array of mappings of the non-alphabetic characters.

static lash * s_global_lash_driver

The global pointer to the LASH driver instance.

static const int c_status_replace

Purely internal constants used with the functions that implement MIDI control for the application.

• static const int c_status_snapshot

This value signals the "snapshot" functionality.

• static const int c_status_queue

This value signals the "queue" functionality.

static rc_settings g_rc_settings

Provides the replacement for all of the other "global_xxx" variables.

• static user_settings g_user_settings

Provides the replacement for all of the other settings in the "user" configuration file, plus some of the "constants" in the globals module.

static const long s handlesize

An internal variable for handle size.

· static const int s_jitter_amount

An internal variable for user-jitter control.

static mainwid * gs_mainwid_pointer

Holds a pointer to the single instance of mainwind for the entire application, once it is created.

const int c mainwid x

The width of the main pattern/sequence grid, in pixels.

- · const int c_mainwid_y
- static perfedit * gs_perfedit_pointer_0

Holds a pointer to the first instance of perfedit for the entire application, once it is created.

static perfedit * gs_perfedit_pointer_1

Holds a pointer to the second instance of perfedit for the entire application, once it is created.

static const long s handlesize

An internal variable for handle size.

11.2.1 Detailed Description

Obsolete Now a permanent option.

0.9.3 delta-tick calculation code. This code doesn't quite work for generating the proper rate of MIDI clocks, and so have disabled that code until we can figure out what it is we're doing wrong. Do not enable it unless you are willing to test it.

Provides a new option to save the Time Signature and Tempo data that may be present in a MIDI file (in the first track) in the sequence object, and write them back to the MIDI file when saved again, in Sequencer64 format. The SeqSpec events that Seq24 and Sequencer64 save for these "events" are not readable by other MIDI applications, such as QTractor. By enabling this macro, other sequencers can read the correct time-signature and tempo values.

```
#define SEQ64_HANDLE_TIMESIG_AND_TEMPO
```

11.2.2 Typedef Documentation

11.2.2.1 midibyte

```
typedef unsigned char seq64::midibyte
```

This can be used for a MIDI buss/port number or for a MIDI channel number. See the SEQ64_INVALID_MIDIBYTE macro.

11.2.2.2 bussbyte

```
typedef unsigned char seg64::bussbyte
```

11.2.2.3 midishort

```
typedef unsigned short seq64::midishort
```

11.2.2.4 midilong

typedef unsigned long seq64::midilong

11.2.2.5 midipulse

typedef long seq64::midipulse

HOWEVER, CURRENTLY, if you make this value unsigned, then perfroll won't show any notes in the sequence bars!!! Also, a number of manipulations of this type currently depend upon it being a signed value.

11.2.3 Enumeration Type Documentation

```
11.2.3.1 wave_type_t
```

enum seq64::wave_type_t

We still have to clarify these type values, though.

Enumerator

WAVE_NONE	
WAVE_SINE	
WAVE_TRIANGLE	
WAVE_INVERSE_TRIANGLE	
WAVE_STEP	

11.2.3.2 seq_modifier_t

enum seq64::seq_modifier_t

We have to tweak the names to avoid redeclaration errors and to "personalize" the values. We change "GDK" to "SEQ64".

Since we're getting events from, say Gtk-2.4, but using our (matching) values for comparison, use the CAST_EQ UIVALENT() macro to compare them. Note that we might still end up having to a remapping (e.g. if trying to get the code to work with the Qt framework).

Enumerator

SEQ64_NO_MASK	
SEQ64_SHIFT_MASK	
SEQ64_LOCK_MASK	
SEQ64_CONTROL_MASK	
SEQ64_MOD1_MASK	
SEQ64_MOD2_MASK	
SEQ64_MOD3_MASK	
SEQ64_MOD4_MASK	

Enumerator

SEQ64_MOD5_MASK	
SEQ64_BUTTON1_MASK	
SEQ64_BUTTON2_MASK	
SEQ64_BUTTON3_MASK	
SEQ64_BUTTON4_MASK	
SEQ64_BUTTON5_MASK	
SEQ64_SUPER_MASK	Bits 13 and 14 are used by XKB, bits 15 to 25 are unused. Bit 29 is used internally.
SEQ64_HYPER_MASK	
SEQ64_META_MASK	
SEQ64_RELEASE_MASK	
SEQ64_MASK_MAX	

11.2.3.3 seq_event_type_t

enum seq64::seq_event_type_t

Only the values we need have been grabbed. We have to tweak the names to avoid redeclaration errors and to "personalize" the values. We change "GDK" to "SEQ64", but, for convenience (to hide errors? :-D), we keep the number the same.

Since we're getting events from, say Gtk-2.4, but using our (matching) values for comparison, use the CAST_EQ UIVALENT() macro to compare them. Note that we might still end up having to a remapping (e.g. if trying to get the code to work with the Qt framework).

Enumerator

SEQ64_NOTHING	
SEQ64_DELETE	
SEQ64_DESTROY	
SEQ64_EXPOSE	
SEQ64_MOTION_NOTIFY	
SEQ64_BUTTON_PRESS	
SEQ64_2BUTTON_PRESS	
SEQ64_3BUTTON_PRESS	
SEQ64_BUTTON_RELEASE	
SEQ64_KEY_PRESS	
SEQ64_KEY_RELEASE	
SEQ64_SCROLL	
SEQ64_EVENT_LAST	

11.2.3.4 seq_scroll_direction_t

enum seq64::seq_scroll_direction_t

We have to tweak the names to avoid redeclaration errors and to "personalize" the values. We change "SEQ64" to "SEQ64".

Since we're getting events from, say Gtk-2.4, but using our (matching) values for comparison, use the CAST_EQ UIVALENT() macro to compare them. Note that we might still end up having to a remapping (e.g. if trying to get the code to work with the Qt framework).

Enumerator

SEQ64_SCROLL_UP	
SEQ64_SCROLL_DOWN	
SEQ64_SCROLL_LEFT	
SEQ64_SCROLL_RIGHT	

11.2.3.5 clock_e

enum seq64::clock_e

This enumeration was also defined in midibus_portmidi.h, but we put it into this common module to avoid duplication.

Enumerator

e_clock_off	Corresponds to the "Off" selection in the MIDI Clock tab. With this setting, the MIDI Clock is disabled for the buss using this setting. Notes will still be sent that buss, of course. Some software synthesizer might require this setting in order to make a sound.
e_clock_pos	Corresponds to the "Pos" selection in the MIDI Clock tab. With this setting, MIDI Clock will be sent to this buss, and, if playback is starting beyond tick 0, then MIDI Song Position and MIDI Continue will also be sent on this buss.
e_clock_mod	Corresponds to the "Mod" selection in the MIDI Clock tab. With this setting, MIDI Clock and MIDI Start will be sent. But clocking won't begin until the Song Position has reached the start modulo (in 1/16th notes) that is specified.

11.2.3.6 interaction_method_t

enum seq64::interaction_method_t

Moved here from the globals.h module.

Enumerator

e_seq24_interaction	Use the normal mouse interactions.
e_fruity_interaction	The "fruity" mouse interactions.
e_number_of_interactions	Keep this last a size value.

11.2.3.7 c_music_scales

enum seq64::c_music_scales

Scales can be shown in the piano roll as gray bars for reference purposes.

We've added three more scales; there are still a number of them that could be fruitfully added to the list of scales. It would be good to offload this stuff into a new "scale" class.

Enumerator

c_scale_off	
c_scale_major	
c_scale_minor	
c_scale_harmonic_minor	
c_scale_melodic_minor	
c_scale_c_whole_tone	
c_scale_blues	
c_scale_major_pentatonic	
c_scale_minor_pentatonic	
c_scale_size	

11.2.3.8 draw_type_t

enum seq64::draw_type_t

These values are used in the sequence, seqroll, perfroll, and mainwid classes.

Enumerator

DRAW_FIN	Indicates that drawing is finished.
DRAW_NORMAL_LINKED	Used for drawing linked notes.
DRAW_NOTE_ON	For starting the drawing of a note.
DRAW_NOTE_OFF	For finishing the drawing of a note.

11.2.3.9 mouse_action_e

enum seq64::mouse_action_e

Enumerator

e_action_select	
e_action_draw	
e action grow	

11.2.3.10 edit_action_t

enum seq64::edit_action_t

These variables represent actions that can be applied to a selection of notes. One idea would be to add a swing-quantize action. We will reserve the value here, for notes only; not yet used or part of the action menu.

Enumerator

c_select_all_notes

Enumerator

c_select_all_events	
c_select_inverse_notes	
c_select_inverse_events	
c_quantize_notes	
c_quantize_events	
c_tighten_events	
c_tighten_notes	
c_transpose_notes	
c_reserved	
c_transpose_h	
c_expand_pattern	
c_compress_pattern	
c_select_even_notes	
c_select_odd_notes	
c_swing_notes	

11.2.4 Function Documentation

11.2.4.1 extract_timing_numbers()

- · measures : beats : divisions
 - "213:4:920"
 - "0:1:0"
- hours : minutes : seconds . fraction
 - "2:04:12.14"
 - "0:1:2"

Warning

This is not the most efficient implementation you'll ever see. At some point we will tighten it up. This function is tested in the seq64-tests project, in the "calculations_unit_test" module.

Parameters

	s	Provides the input time string, in measures or time format, to be processed.	
out	part←	The destination reference for the first part of the time.	
	_1		
out	part⇔	The destination reference for the second part of the time.	
	_2		
out	part⇔	The destination reference for the third part of the time.	Generated by Doxygen
	_3		
out	fraction	The destination reference for the fractional part of the time.	

Returns

Returns true if a reasonable portion (3 numbers) was good for extraction. The fraction part will start with a period for easier conversion to fractional seconds.

11.2.4.2 pulses_to_string()

```
\begin{tabular}{ll} {\tt std::string seq64::pulses\_to\_string (} \\ & {\tt midipulse } p \end{tabular} \end{tabular}
```

Todo Still needs to be unit tested.

Parameters

p | The MIDI pulse/tick value to be converted.

Returns

Returns the string as an unsigned ASCII integer number.

11.2.4.3 pulses_to_measurestring()

```
std::string seq64::pulses_to_measurestring (
    midipulse p,
    const midi_timing & seqparms)
```

Parameters

p	The number of MIDI pulses (clocks, divisions, ticks, you name it) to be converted. If the value is SEQ64_NULL_MIDIPULSE, it is converted to 0, because callers don't generally worry about such niceties, and the least we can do is convert illegal measure-strings (like "000:0:000") to a legal value.
seqparms	This small structure provides the beats/measure, beat-width, and PPQN that hold for the sequence involved in this calculation. These values are needed in the calculations.

Returns

Returns the string, in measures notation, for the absolute pulses that mark this duration.

11.2.4.4 pulses_to_midi_measures()

	р	Provides the MIDI pulses (as in "pulses per quarter note") that are to be converted to MIDI measures format.
	seqparms	This small structure provides the beats/measure (B), beat-width (W), and PPQN (P) that hold for the sequence involved in this calculation. The beats/minute (T for tempo) value is not needed.
out	measures	Provides the current MIDI song time structure to hold the results, which are the measures, beats, and divisions values for the time of interest. Note that the measures and beats are corrected to be re 1, not 0.

Returns

Returns true if the calculations were able to be made. The P, B, and W values all need to be greater than 0.

If the fraction part is 0, then it is not shown. Examples:

```
- "0:0:0"

- "0:0:0.102333"

- "12:3:1"

- "12:3:1.000001"
```

Parameters

р	Provides the number of ticks, pulses, or divisions in the MIDI event time.
bpm	Provides the tempo of the song, in beats/minute.
ppqn	Provides the pulses-per-quarter-note of the song.

Returns

Returns the time-string representation of the pulse (ticks) value.

See the other pulses_to_timestring() overload.

Todo Still needs to be unit tested.

р	Provides the number of ticks, pulses, or divisions in the MIDI event time.
timinginfo	Provides the tempo of the song, in beats/minute, and the pulse-per-quarter-note of the song.

Returns

Returns the return-value of the other pulses_to_timestring() function.

11.2.4.7 measurestring_to_pulses()

Parameters

measures	Provides the current MIDI song time in "measures:beats:divisions" format, where divisions are the MIDI pulses in "pulses-per-quarter-note".
seqparms	This small structure provides the beats/measure, beat-width, and PPQN that hold for the sequence involved in this calculation.

Returns

Returns the absolute pulses that mark this duration. If the input string is empty, then 0 is returned.

11.2.4.8 midi_measures_to_pulses()

p = 4 * P * m * B / W p == pulse count (ticks or pulses) m == number of measures B == beats per measure (constant) P == pulses per quarter-note (constant) W == beat width in beats per measure (constant)

Note that the 0-pulse MIDI measure is "1:1:0", which means "at the beginning of the first beat of the first measure, no pulses'. It is not "0:0:0" as one might expect.

Parameters

measures	Provides the current MIDI song time structure holding the measures, beats, and divisions values
	for the time of interest.
seqparms	This small structure provides the beats/measure, beat-width, and PPQN that hold for the
	sequence involved in this calculation.

Returns

Returns the absolute pulses that mark this duration. If the pulse-value cannot be calculated, then SEQ64 $_{\leftarrow}$ NULL_MIDIPULSE is returned.

11.2.4.9 timestring_to_pulses()

Parameters

timestring	The time value to be converted, which must be of the form "hh:mm:ss" or "hh:mm:ss.fraction".
bpm	The beats-per-minute tempo (e.g. 120) of the current MIDI song.
ppqn	The parts-per-quarter note precision (e.g. 192) of the current MIDI song.

Returns

Returns 0 if an error occurred or if the number actually translated to 0.

This conversion assumes that the fractional parts of the seconds is padded with zeroes on the left or right to 6 digits.

This conversion assumes that the fractional parts of the seconds is padded with zeroes on the left or right to 6 digits.

11.2.4.10 string_to_pulses()

First, the type of string is deduced by the characters in the string. If the string contains two colons and a decimal point, it is assumed to be a time-string ("hh:mm:ss.frac"); in addition ss will have to be less than 60.

If the string just contains two colons, then it is assumed to be a measure-string ("measures:beats:divisions").

If it has none of the above, it is assumed to be pulses. Testing is not rigorous.

Parameters

s	Provides the string to convert to pulses.
mt	Provides the structure needed to provide BPM and other values needed for some of the conversions done by this function.

Returns

Returns the string as converted to MIDI pulses (or divisions, clocks, ticks, whatever you call it).

11.2.4.11 string_to_midibyte()

```
midibyte seq64::string_to_midibyte ( {\tt const\ std::string\ \&\ s\ )}
```

This function bypasses characters until it finds a digit (whether part of the number or a "0x" construct), and then converts it.

s Provides the string to convert to a MIDI byte.

Returns

Returns the MIDI byte value represented by the string.

11.2.4.12 shorten_file_spec()

This is done by removing character in the middle, if necessary, and replacing them with an ellipse.

This function operates by first trying to find the <code>/home directory</code>. If found, it strips off <code>/home/username and replace</code> it with the Linux \sim replacement for the <code>\$HOME</code> environment variable. This function assumes that the "username" portion *must* exist, and that there's no goofy stuff like double-slashes in the path.

Parameters

fpath	The file specification, including the full path to the file, and the name of the file.
leng	Provides the length to which to limit the string.

Returns

Returns the fpath parameter, possibly shortened to fit within the desired length.

11.2.4.13 string_not_void()

Provides essentially the opposite test that string_is_void() provides. The definition of white-space is provided by the std::isspace() function/macro.

Parameters

s The string pointer to check for emptiness.

Returns

Returns true if the pointer is valid, the string has a non-zero length, and is not just white-space.

11.2.4.14 string_is_void()

```
bool seq64::string_is_void ( {\tt const\ std::string\ \&\ s\ )}
```

Meant to have essentially the opposite result of string_not_void(). The meaning of empty is special here, as it refers to a string being useless as a token:

```
    The string is of zero length.
    The string has only white-space characters in it, where the isspace() macro provides the definition of white-space.
```

Parameters

```
s The string pointer to check for emptiness.
```

Returns

Returns true if the string has a zero length, or is only white-space.

11.2.4.15 strings_match()

The strings_match() function returns true if the comparison items are identical, without case-sensitivity in character content up to the length of the secondary string. This allows abbreviations to match. (And, in scanning routines, the first match is immediately accepted.)

Parameters

target	The primary string in the comparison. This is the target string, the one we hope to match. It is assumed to be non-empty, and the result is false if it is empty.
X	The secondary string in the comparison. It must be no longer than the target string, or the match is
	false.

Returns

Returns true if both strings are are identical in characters, up to the length of the secondary string, with the case of the characters being insignificant. Otherwise, false is returned.

11.2.4.16 log2_time_sig_value()

Useful in converting a time signature's denominator to a Time Signature meta event's "dd" value.

tsd The time signature denominator, which must be a power of 2: 2, 4, 8, 16, or 32.

Returns

Returns the power of 2 that achieves the tsd parameter value.

11.2.4.17 tempo_us_to_bytes()

Recall the format of a Tempo event:

0 FF 51 03 t2 t1 t0 (tempo as number of microseconds per quarter note)

This code is the inverse of the lines of code around line 768 in midifile.cpp, which is basically ((t2 * 256) + t1) * 256 + t0.

As a test case, note that the default tempo is 120 beats/minute, which is equivalent to ttttt=500000 (0x07A120).

Parameters

t	Provides a small array of 3 elements to hold each tempo byte.
tempo_us	Provides the temp value in microseconds per quarter note.

11.2.4.18 zoom_power_of_2()

The default starting zoom is 2, but this value is suitable only for PPQN of 192 and below. Also, zoom currently works consistently only if it is a power of 2. For starters, we scale the zoom to the selected ppqn, and then shift it each way to get a suitable power of two.

Parameters

ppqn	The ppqn of interest.

Returns

Returns the power of 2 appropriate for the given PPQN value.

11.2.4.19 beats_per_minute_from_tempo_us()

The tempo event's numeric value is given in 3 bytes, and is in units of microseconds-per-quarter-note (us/qn).

Parameters

tempo The value of the Tempo meta-event, in units of us/qn. If this value is 0, we'll get an arithmetic exception.

Returns

Returns the beats per minute. If the tempo value is too small, then this function will crash. :-D

11.2.4.20 tempo_us_from_beats_per_minute()

Parameters

bpm The value of beats-per-minute. If this value is 0, we'll get an arithmetic exception.

Returns

Returns the tempo in qn/us. If the bpm value is too small, then this function will crash. :-D

11.2.4.21 tempo_to_us()

120 beats/minute) to microseconds.

Parameters

bpm Provides the tempo in beats/minute.

11.2.4.22 pulse_length_us()

The formula for the pulse-length in seconds is:

bpm	Provides the beats-per-minute value. No sanity check is made. If this value is 0, we'll get an arithmetic exception.
ppqn	Provides the pulses-per-quarter-note value. No sanity check is made. If this value is 0, we'll get an arithmetic exception.

Returns

Returns the pulse length in microseconds. If either parameter is invalid, then this function will crash. :-D

11.2.4.23 delta_time_us_to_ticks()

```
double seq64::delta_time_us_to_ticks (
          unsigned long us,
          int bpm,
          int ppqn ) [inline]
```

This function is the inverse of ticks to delta time us().

Please note that terms "ticks" and "pulses" are equivalent, and refer to the "pulses" in "pulses per quarter note".

```
beats pulses 1 minute 1 sec
P = 120 ----- * 192 ----- * T us * ------ * -----
minute beats 60 sec 1,000,000 us
```

Note that this formula assumes that a beat is a quarter note. If a beat is an eighth note, then the P value would be halved, because there would be only 96 pulses per beat. We will implement an additional function to account for the beat; the current function merely blesses some calculations made in the application.

Parameters

us	The number of microseconds in the delta time.
bpm	Provides the beats-per-minute value, otherwise known as the "tempo".
ppqn	Provides the pulses-per-quarter-note value, otherwise known as the "division".

Returns

Returns the tick value.

11.2.4.24 ticks to delta time us()

The inverse of delta_time_us_to_ticks().

Please note that terms "ticks" and "pulses" are equivalent, and refer to the "pulses" in "pulses per quarter note".

Old: 60000000.0 * double(delta_ticks) / (double(bpm) * double(ppqn));

Parameters

delta_ticks	The number of ticks or "clocks".
bpm	Provides the beats-per-minute value, otherwise known as the "tempo".
ppqn	Provides the pulses-per-quarter-note value, otherwise known as the "division".

Returns

Returns the time value in microseconds.

11.2.4.25 clock_tick_duration_bogus()

Deprecated This is a somewhat bogus calculation used only for "statistical" output in the old perform module. Name changed to reflect this unfortunate fact. Use pulse_length_us() instead.

```
60000000 ppqn

us = -------

MIDI_CLOCK_IN_PPQN * bpm * ppqn

MIDI_CLOCK_IN_PPQN is 24.
```

Parameters

bpm	Provides the beats-per-minute value. No sanity check is made. If this value is 0, we'll get an arithmetic exception.
ppqn	Provides the pulses-per-quarter-note value. No sanity check is made. If this value is 0, we'll get an arithmetic exception.

Returns

Returns the clock tick duration in microseconds. If either parameter is invalid, this will crash. Who wants to waste time on value checks here? :-D

11.2.4.26 clock_ticks_from_ppqn()

ppqn The number of pulses per quarter note. For example, the default value for Seq24 is 192.

Returns

The integer value of ppqn / 24 [MIDI_CLOCK_IN_PPQN] is returned.

11.2.4.27 double_ticks_from_ppqn()

The same as clock_ticks_from_ppqn(), but returned as a double float.

Parameters

```
ppqn The number of pulses per quarter note.
```

Returns

The double value of ppqn / 24 [SEQ64_MIDI_CLOCK_IN_PPQN]_is returned.

11.2.4.28 pulses_per_measure()

```
midipulse seq64::pulses_per_measure (
    int ppqn = SEQ64_DEFAULT_PPQN ) [inline]
```

This calculation is extremely simple, and it provides an important constraint to pulse (ticks) calculations: the number of pulses in a measure is always 4 times the PPQN value, regardless of the time signature. The number pulses in a 7/8 measure is the the same as in a 4/4/ measure.

11.2.4.29 measures_to_ticks()

This function is called in seqedit::apply_length(), when the user selects a sequence length in measures. That function calculates the length in ticks. The number of pulses is given by the number of quarter notes times the pulses per quarter note. The number of quarter notes is given by the measures times the quarter notes per measure. The quarter notes per measure is given by the beats per measure times 4 divided by beat_width beats. So:

```
p = 4 * P * m * B / W
    p == pulse count (ticks or pulses)
    m == number of measures
    B == beats per measure (constant)
    P == pulses per quarter-note (constant)
    W == beat width in beats per measure (constant)
```

```
For our "b4uacuse" MIDI file, M can be about 100 measures, B is 4, P can be 192 (but we want to support higher values), and W is 4. So p = 100 * 4 * 4 * 192 / 4 = 76800 ticks. Note that 4 * P is a constraint encapsulated by the inline function pulses_per_measure().
```

bpm	The B value in the equation, beats/measure.
ppqn	The P value in the equation, pulses/qn.
bw	The W value in the equation, the denominator of the time signature. If this value is 0, we'll get an arithmetic exception (crash), so we just return 0 in this case.
measures	The M value in the equation. It defaults to 1, in case one desires a simple "ticks per measure"
	number.

Returns

Returns the L value (ticks or pulses) as calculated via the given equation. If bw is 0, then 0 is returned.

11.2.4.30 wave_func()

We extracted this function from mattias's Ifownd module, as it is more generally useful.

Parameters

angle		Provides the radial angle to be applied.
wavet	уре	Provides the wave_type_t value to select the type of wave data-point to be generated.

11.2.4.31 help_check()

Also check for the –legacy option. Finally, it also checks for the "?" option that people sometimes use as a guess to get help.

Parameters

argc	The number of command-line arguments.
argv	The array of command-line argument pointers.

Returns

Returns true only if -v, -V, -version, -h, -help, or "?" were encountered. If the legacy options occurred, then rc().legacy_format(true) is called, as a side effect, because it will be needed before we parse the options.

11.2.4.32 parse_options_files()

It probably requires this call preceding: Gtk::Main kit(argc, argv), to strip any GTK+-specific parameters the knowledgeable user may have added. Usage:

```
Gtk::Main kit(argc, argv);
seq64::gui_assistant_gtk2 gui;
seq64::perform p(gui);
```

It also requires the caller to call rc().set_defaults() and usr().set_defaults(). The caller can then use the command-line to make any modifications to the setting that will be used here. The biggest example is the -r/-reveal-alsa-ports option, which determines if the MIDI buss definition strings are read from the 'user' configuration file.

Instead of the legacy Seq24 names, we use the new configuration file-names, located in the \sim /.config/sequencer64 directory. However, if they are not found, we no longer fall back to the legacy configuration file-names. If the – legacy option is in force, use only the legacy configuration file-name. The code also ensures the directory exists. CURRENTLY LINUX-SPECIFIC. See the rc_settings class for how this works.

```
std::string cfg_dir = seq64::rc().home_config_directory();
if (cfg_dir.empty())
    return EXIT_FAILURE;
```

Change Note ca 2016-04-03 We were parsing the user-file first, but we now need to parse the rc-file first, to get the manual-alsa-ports option, so that we can avoid overriding the port names that the ALSA system provides, if the manual-alsa-option is false.

Parameters

р	Provides the perform object that will be affected by the new parameters.
argc	The number of command-line arguments.
argv	The array of command-line argument pointers.

Returns

Returns true if the reading of both configuration files succeeded.

11.2.4.33 parse_command_line_options()

```
int argc,
char * argv[] )
```

Note that, since we call this function twice (once before the configuration files are parsed, and once after), we have to make sure that the global value optind is reset to 0 before calling this function. Note that the traditional reset value for optind is 1, but 0 is used in GNU code to trigger the internal initialization routine of get_opt().

Parameters

argc	The number of command-line arguments.
argv	The array of command-line argument pointers.

Returns

Returns the value of optind if no help-related options were provided.

11.2.4.34 write_options_files()

This function gets any legacy global variables, on the theory that they might have been changed.

Parameters

p Provides the perform object that may provide new values for the parameters.

Returns

Returns true if both files were saved successfully. Otherwise returns false. But even if one write failed, the other might have succeeded.

11.2.4.35 build_details()

```
std::string seq64::build_details ( )
```

Returns

Returns an ordered, human-readable string enumerating the built-in features of this application.

11.2.4.36 to_string()

Nothing fancy. If you want that, use the midicvt project.

ev The event to put on show.

Returns

Returns the string representation of the event parameter.

11.2.4.37 file_access()

11.2.4.38 file_exists()

Parameters

filename | Provides the name of the file to be checked.

Returns

Returns 'true' if the file exists.

11.2.4.39 file_readable()

Parameters

filename Provides the name of the file to be checked.

Returns

Returns 'true' if the file is readable.

11.2.4.40 file_writable()

filename	Provides the name of the file to be checked.	
----------	--	--

Returns

Returns 'true' if the file is writable.

11.2.4.41 file_accessible()

An even stronger test than file_exists. At present, we see no need to distinguish read and write permissions. We assume the file is accessible only if the file has both permissions.

Parameters

Returns

Returns 'true' if the file is readable and writable.

11.2.4.42 file_executable()

Parameters

filename Provides the name of the file to be checked	l.
--	----

Returns

Returns 'true' if the file exists.

11.2.4.43 file_is_directory()

This function is also used in the function of the same name in fileutilities.cpp.

Parameters

filonamo	Provides the name of the directory to be checked.
IIIGHAHIG	I TOVIDES THE HATTE OF THE UITECTOLY TO DE CHECKEU.

Returns

Returns 'true' if the file is a directory.

11.2.4.44 make_directory()

This function is actually a little more general than that, but it is not sufficiently general, in general.

Parameters

pathname

Provides the name of the path to create. The parent directory of the final directory must already exist.

Returns

Returns true if the path-name exists.

11.2.4.45 ppqn_is_valid()

Validates a PPQN value.

Parameters

```
ppqn Provides the PPQN value to be used.
```

Returns

Returns true if the ppqn parameter is between MINIMUM_PPQN and MAXIMUM_PPQN, or is set to SE

Q64_USE_DEFAULT_PPQN (-1).

11.2.4.46 jack_sync_callback()

```
int seq64::jack_sync_callback (
          jack_transport_state_t state,
          jack_position_t * pos,
          void * arg )
```

This JACK synchronization callback informs the specified perform object of the current state and parameters of JACK.

The transport state will be:

- JackTransportStopped when a new position is requested.
 JackTransportStarting when the transport is waiting to start.
 JackTransportRolling when the timeout has expired, and the
 - position is now a moving target.

This is the slow-sync callback, which the stazed code replaces with jack_process_callback().

state	The JACK Transport state.
pos	The JACK position value.
arg	The pointer to the jack_assistant object. Currently not checked for nullity, nor dynamic-casted.

Returns

Returns 1 if the function works, and 0 if something was wrong.

11.2.4.47 jack_shutdown_callback()

Parameters

ara

Points to the jack_assistant in charge of JACK support for the perform object.

11.2.4.48 jack_timebase_callback()

```
void seq64::jack_timebase_callback (
    jack_transport_state_t state,
    jack_nframes_t nframes,
    jack_position_t * pos,
    int new_pos,
    void * arg )
```

The original version of the function worked properly with Hydrogen, but not with Klick. The new code seems to work with both. More testing and clarification is needed. This new code was "discovered" in the source-code for the "SooperLooper" project:

```
http://essej.net/sooperlooper/
```

The first difference with the new code is that it handles the case where the JACK position is moved (new_pos == true). If this is true, and the JackPositionBBT bit is off in pos->valid, then the new BBT value is set.

The seconds set of differences are in the "else" clause. In the new code, it is very simple: calculate the new tick value, back it off by the number of ticks in a beat, and perhaps go to the first beat of the next bar.

In the old code (complex!), the simple BBT adjustment is always made. This changes (perhaps) the beats_per_bar, beat_type, etc. We need to make these settings use the actual global values for beats set for Sequencer64. Then, if transitioning from JackTransportStarting to JackTransportRolling (instead of checking new_pos!), the BBT values (bar, beat, and tick) are finally adjusted. Here are the steps, with old and new steps noted:

```
-# Calculate the "delta" ticks based on the current frame, the
    ticks_per_beat, the beats_per_minute, and the frame_rate. The old
    code saves this in a local, the new code assigns it to pos->tick.
-# Old code: save this delta as a positive value.
-# Figure out the settings and modify bar, beat, tick, and
    bar_start_tick. The old and new code seem to have the same intent,
    but it seems like the new code is faster and also correct.
- Old code: Calculations are made by division and mod
        operations.
- New code: Calculations are made by increments and decrements
    in a while loop.
```

Stazed:

The call to jack_timebase_callback() to supply JACK with BBT, etc. would occasionally fail when the pos information had zero or some garbage in the pos.frame_rate variable. This would occur when there was a rapid change of frame position by another client... i.e. qjackctl. From the JACK API:

pos address of the position structure for the next cycle; pos->frame will be its frame number. If new_pos is FALSE, this structure contains extended position information from the current cycle. If TRUE, it contains whatever was set by the requester. The timebase_callback's task is to update the extended information here."

The "If TRUE" line seems to be the issue. It seems that qjackctl does not always set pos.frame_rate so we get garbage and some strange BBT calculations that display in qjackctl. So we need to set it here and just use m_jack_frame_rate for calculations instead of pos.frame_rate.

Parameters

state	Indicates the current state of JACK transport.
nframes	The number of JACK frames in the current time period.
pos	Provides the position structure to be filled in, the address of the position structure for the next cycle; pos->frame will be its frame number. If new_pos is FALSE, this structure contains extended position information from the current cycle. If TRUE, it contains whatever was set by the requester. The timebase_callback's task is to update the extended information here.
new_pos	TRUE (non-zero) for a newly requested pos, or for the first cycle after the timebase_callback is defined. This is usually 0 in Sequencer64 at present, and 1 if one, say, presses "rewind" in qjackctl.
arg	Provides the jack_assistant pointer, currently unchecked for nullity.

11.2.4.49 jack_process_callback()

```
int seq64::jack_process_callback (
          jack_nframes_t nframes,
          void * arg )
```

11.2.4.50 get_current_jack_position()

11.2.4.51 jack_session_callback()

```
void seq64::jack_session_callback (
          jack_session_event_t * ev,
          void * arg )
```

Glib is then used to connect in perform::jack_session_event(). However, the perform object's GUI-support interface is used instead of the following, so that the libseq64 library can be independent of a specific GUI framework:

```
Glib::signal_idle().
    connect(sigc::mem_fun(*jack, &jack_assistant::session_event));
```

ev	The JACK event to be set.	
arg	The pointer to the jack_assistant object. Currently not checked for nullity.	

11.2.4.52 invalid_key()

unsigned int key)

In gtkmm, this is done via the gdk_keyval_name() function. Here, in the base class, we just provide an easy-to-create string. Note that this is a free function, not a class member.

Parameters

key Provides the key-number to be converted to a key r
--

Returns

Returns the key name as looked up by the GDK infrastructure. If the key is not found, then an empty string is returned.

11.2.4.54 keyval_normalize()

Otherwise, random values, unchecked, can cause the application to crash.

Any field that is 0 or greater than 65536 is fixed. Not perfect, but better than allowing random values to be used.

Parameters

k The structure to be validated and normalized.

11.2.4.55 create_lash_driver()

Initializes the lash driver (strips lash-specific command line arguments), then connects to the LASH daemon and polls events.

This function will always be called from the main routine, and called only once. Note that we don't need that darn SEQ64_LASH_SUPPORT macro in client code anymore.

Parameters

р	The perform object that needs to implement LASH support.
argc	The number of command-line arguments.
argv	The command-line arguments.

Returns

This function returns true if a lash object was created. This function will not create one if not configured to, if the command-line options did not specify the creation of the LASH driver, or if the LASH driver was already created.

11.2.4.56 lash_driver()

```
lash * seq64::lash_driver ( )
```

Returns

Returns the pointer to the LASH driver if it exists. Otherwise a null pointer is returned. The caller *must always check* the return value.

11.2.4.57 delete_lash_driver()

```
void seq64::delete_lash_driver ( )
```

This function will always be called from the main routine, once. The other lash-pointer functions will know if the pointer has been deleted.

11.2.4.58 is_null_midipulse()

By "null" in this case, we mean "unusable", not 0. Sigh, it's always something.

11.2.4.59 output_thread_func()

Set up the performance, set the process to realtime privileges, and then start the output function.

myperf

Provides the perform object instance that is to be used. Its output_func() is called. Currently, this parameter is not validated, for speed.

Returns

Always returns nullptr.

11.2.4.60 input_thread_func()

Parameters

myperf

Provides the perform object instance that is to be used. Its output_func() is called. Currently, this parameter is not validated, for speed.

Returns

Always returns nullptr.

11.2.4.61 rc()

```
rc_settings & seq64::rc ()
```

Why a function instead of direct variable access? Encapsulation. We are then free to change the way "global" settings are accessed, without changing client code.

Returns

Returns the global object g_rc_settings.

11.2.4.62 usr()

```
user_settings & seq64::usr ( )
```

Returns

Returns the global object g_user_settings.

11.2.4.63 choose_ppqn()

Putting it here means we can reduce the reliance on the global ppqn.

ppqn	Provides the PPQN value to be used.
------	-------------------------------------

Returns

Returns the ppqn parameter, unless that parameter is SEQ64_USE_DEFAULT_PPQN (-1), then usr().midi ← _ppqn is returned.

11.2.4.64 min()

```
long seq64::min (
          long a,
          long b) [inline]
```

Parameters

а	First operand.
b	Second operand.

Returns

Returns the minimum value of a and b.

11.2.4.65 make_section_name()

Parameters

label	The base-name of the section.
value	The numeric value to append to the section name.

Returns

Returns a string of the form "[basename-1]".

11.2.4.66 font_render()

```
font& seq64::font_render ( ) [inline]
```

We've going to render this pointer obsolete, though, and use a smart factory function to ensure the existence of this pointer, and return a reference to the font object.

We wanted to make the font a const object, but mainwid::on_realize() calls the font::init() function with its window object, and using const is impractical. We don't want to force every caller to deal with the overhead of passing even a null window pointer, either.

However, at some point we need some quarantee that the init() function is called before rendering a string. Right now, we guarantee it only by build order.

Returns

Returns a reference to the object pointed to by sp_font_renderer.

11.2.4.67 adjustment_dummy()

```
Gtk::Adjustment & seq64::adjustment_dummy ( )
```

This static object is used so we have an Adjustment to assign to the Adjustment members for classes that don't use them. Clumsy? We shall see.

Anyway, the parameters for this constructor are value, lower, upper, step-increment, and two more values.

11.2.4.68 update_mainwid_sequences()

```
void seq64::update_mainwid_sequences ( )
```

It is used by other objects that can modify the currently-edited sequence shown in the mainwid (main window).

11.2.4.69 update_perfedit_sequences()

```
void seq64::update_perfedit_sequences ( )
```

It is used by other objects (seqedit and eventedit) that can modify the currently-edited sequence shown in the perfedit (song window).

11.2.4.70 FF_RW_timeout()

Parameters

arg | Provide a putative pointer to the perform object.

Returns

Returns the value of the perform::FF_RW_timeout() call if Seq32 transport support is enabled and the arg parameter is good, otherwise false is returned.

11.2.5 Variable Documentation

11.2.5.1 c_controller_names

```
std::string seq64::c_controller_names
```

This array is used only by the segedit class.

11.2.5.2 EVENT_STATUS_BIT

```
const midibyte seq64::EVENT_STATUS_BIT
```

11.2.5.3 **EVENT_ANY**

```
const midibyte seq64::EVENT_ANY
```

The following MIDI events are channel messages. The comments represent the one or two data-bytes of the message.

Note that Channel Mode Messages use the same code as the Control Change, but uses reserved controller numbers ranging from 122 to 127.

The EVENT_ANY (0x00) value may prove to be useful in allowing any event to be dealt with. Not sure yet, but the cost is minimal.

11.2.5.4 EVENT_NOTE_OFF

```
const midibyte seq64::EVENT_NOTE_OFF
```

11.2.5.5 EVENT_NOTE_ON

```
const midibyte seq64::EVENT_NOTE_ON
```

11.2.5.6 EVENT_AFTERTOUCH

```
const midibyte seq64::EVENT_AFTERTOUCH
```

11.2.5.7 EVENT_CONTROL_CHANGE

```
const midibyte seq64::EVENT_CONTROL_CHANGE
```

11.2.5.8 EVENT_PROGRAM_CHANGE

```
const midibyte seq64::EVENT_PROGRAM_CHANGE
```

11.2.5.9 EVENT_CHANNEL_PRESSURE

```
const midibyte seq64::EVENT_CHANNEL_PRESSURE
```

11.2.5.10 EVENT_PITCH_WHEEL

```
const midibyte seq64::EVENT_PITCH_WHEEL
```

11.2.5.11 EVENT_MIDI_SYSEX

```
const midibyte seq64::EVENT_MIDI_SYSEX
```

The following MIDI events have no channel. We have included redundant constant variables for the SysEx Start and End bytes just to make it clear that they are part of this sequence of values, though usually treated separately.

Only the following constants are followed by some data bytes:

```
- EVENT_MIDI_SYSEX = 0xF0
- EVENT_MIDI_QUARTER_FRAME = 0xF1 // undefined?
- EVENT_MIDI_SONG_POS = 0xF2
- EVENT_MIDI_SONG_SELECT = 0xF3
```

A MIDI System Exclusive (SYSEX) message starts with F0, followed by the manufacturer ID (how many? bytes), a number of data bytes, and ended by an F7.

11.2.5.12 EVENT_MIDI_QUARTER_FRAME

```
const midibyte seq64::EVENT_MIDI_QUARTER_FRAME
```

11.2.5.13 EVENT_MIDI_SONG_POS

```
const midibyte seq64::EVENT_MIDI_SONG_POS
```

```
11.2.5.14 EVENT_MIDI_SONG_SELECT
const midibyte seq64::EVENT_MIDI_SONG_SELECT
11.2.5.15 EVENT_MIDI_SONG_F4
const midibyte seq64::EVENT_MIDI_SONG_F4
11.2.5.16 EVENT_MIDI_SONG_F5
const midibyte seq64::EVENT_MIDI_SONG_F5
11.2.5.17 EVENT_MIDI_TUNE_SELECT
const midibyte seq64::EVENT_MIDI_TUNE_SELECT
11.2.5.18 EVENT_MIDI_SYSEX_END
const midibyte seq64::EVENT_MIDI_SYSEX_END
11.2.5.19 EVENT_MIDI_SYSEX_CONTINUE
const midibyte seq64::EVENT_MIDI_SYSEX_CONTINUE
11.2.5.20 EVENT_MIDI_CLOCK
const midibyte seq64::EVENT_MIDI_CLOCK
11.2.5.21 EVENT_MIDI_SONG_F9
const midibyte seq64::EVENT_MIDI_SONG_F9
11.2.5.22 EVENT_MIDI_START
const midibyte seq64::EVENT_MIDI_START
11.2.5.23 EVENT_MIDI_CONTINUE
```

const midibyte seq64::EVENT_MIDI_CONTINUE

11.2.5.24 EVENT_MIDI_STOP

const midibyte seq64::EVENT_MIDI_STOP

11.2.5.25 EVENT_MIDI_SONG_FD

const midibyte seq64::EVENT_MIDI_SONG_FD

11.2.5.26 EVENT_MIDI_ACTIVE_SENS

const midibyte seq64::EVENT_MIDI_ACTIVE_SENS

11.2.5.27 EVENT MIDI RESET

const midibyte seq64::EVENT_MIDI_RESET

11.2.5.28 EVENT_MIDI_META

const midibyte seq64::EVENT_MIDI_META

11.2.5.29 EVENT_NULL_CHANNEL

const midibyte seq64::EVENT_NULL_CHANNEL

However, it also means that the channel is encoded in the m_status byte itself. This is our work around to be able to hold a multi-channel SMF 0 track in a sequence. In a Sequencer64 SMF 0 track, every event has a channel. In a Sequencer64 SMF 1 track, the events do not have a channel. Instead, the channel is a global value of the sequence, and is stuffed into each event when the event is played or is written to a MIDI file.

11.2.5.30 EVENT_GET_CHAN_MASK

const midibyte seq64::EVENT_GET_CHAN_MASK

11.2.5.31 EVENT_CLEAR_CHAN_MASK

const midibyte seq64::EVENT_CLEAR_CHAN_MASK

11.2.5.32 EVENTS_ALL

const int seq64::EVENTS_ALL

We reversed the parts of each token for consistency with the macros defined above.

11.2.5.33 EVENTS_UNSELECTED

```
const int seq64::EVENTS_UNSELECTED
```

11.2.5.34 c_midibus_output_size

```
const int seq64::c_midibus_output_size
```

These constants were also defined in midibus_portmidi.h, but we made them common to both implementations here

The c_midibus_output_size value is passed, in mastermidibus, to snd_seq_set_output_buffer_size(). Not sure if the value needs to be so large.

11.2.5.35 c_midibus_input_size

```
const int seq64::c_midibus_input_size
```

Not sure if the value needs to be so large.

11.2.5.36 c_midibus_sysex_chunk

```
const int seq64::c_midibus_sysex_chunk
```

11.2.5.37 c_midibus

```
const midilong seq64::c_midibus
```

Some of the information is stored with each track (and in the midi_container-derived classes), and some is stored in the proprietary header.

Track (sequencer-specific) data:

```
c_midibus
c_midich
c_timesig
c_triggers (deprecated)
c_triggers_new
c_musickey (can be in footer, as well)
c_musicscale (ditto)
c_backsequence (ditto)
c_transpose
```

Footer ("proprietary") data:

```
c_midictrl
c_midiclocks
c_notes
c_bpmtag (beats per minute)
c_mutegroups
c_perf_bp_mes (perfedit's beats-per-measure setting)
c_perf_bw (perfedit's beat-width setting)
```

Also see the PDF file in the following project for more information about the "proprietary" data:

https://github.com/ahlstromcj/sequencer64-doc.git

Note that the track data is read from the MIDI file, but not written directly to the MIDI file. Instead, it is stored in the MIDI container as sequences are edited to used these "sequencer-specific" features. Also note that c_triggers has been replaced by c_triggers_new as the code that marks the triggers stored with a sequence.

As an extension, we can also grab the key, scale, and background sequence value selected in a sequence and write these values as track data, where they can be read in and applied to a specific sequence, when the sequence object is created. These values would not be stored in the legacy format.

Something like this could be done in the "user" configuration file, but then the key and scale would apply to all songs. We don't want that.

We could also add snap and note-length to the per-song defaults, but the "user" configuration file seems like a better place to store these preferences.

Note

The new value c_transpose value is from Stazed's seq32 project. The code to support this option is turned on via the build-configurable SEQ64_STAZED_TRANSPOSE macro, but here we reserved the value even if that option is not enabled by the user. There are additional values from Stazed/seq32, not yet used. Track buss number.

11.2.5.38 c_midich

const midilong seq64::c_midich

11.2.5.39 c_midiclocks

const midilong seq64::c_midiclocks

11.2.5.40 c_triggers

const midilong seq64::c_triggers

11.2.5.41 c_notes

const midilong seq64::c_notes

11.2.5.42 c_timesig

const midilong seq64::c_timesig

```
11.2.5.43 c_bpmtag
const midilong seq64::c_bpmtag
11.2.5.44 c_triggers_new
const midilong seq64::c_triggers_new
11.2.5.45 c_mutegroups
const midilong seq64::c_mutegroups
11.2.5.46 c_midictrl
const midilong seq64::c_midictrl
11.2.5.47 c_musickey
const midilong seq64::c_musickey
11.2.5.48 c_musicscale
const midilong seq64::c_musicscale
11.2.5.49 c_backsequence
const midilong seq64::c_backsequence
11.2.5.50 c_transpose
const midilong seq64::c_transpose
11.2.5.51 c_perf_bp_mes
const midilong seq64::c_perf_bp_mes
11.2.5.52 c_perf_bw
const midilong seq64::c_perf_bw
```

```
11.2.5.53 c_midi_track_ctrl
```

```
const int seq64::c_midi_track_ctrl
```

The lowest value is $c_{seqs_in_set} * 2 = 64$.

I think the reason for that value is to perhaps handle two sets or something like that. Will figure it out later.

The controls are read in from the "rc" configuration files, and are written to the c_midictrl section of the "proprietary" final track in a Seq24/Sequencer64 MIDI file.

11.2.5.54 c_midi_control_bpm_up

```
const int seq64::c_midi_control_bpm_up
```

11.2.5.55 c_midi_control_bpm_dn

const int seq64::c_midi_control_bpm_dn

11.2.5.56 c midi control ss up

const int seq64::c_midi_control_ss_up

11.2.5.57 c_midi_control_ss_dn

const int seq64::c_midi_control_ss_dn

11.2.5.58 c_midi_control_mod_replace

const int seq64::c_midi_control_mod_replace

11.2.5.59 c_midi_control_mod_snapshot

const int seq64::c_midi_control_mod_snapshot

11.2.5.60 c_midi_control_mod_queue

const int seq64::c_midi_control_mod_queue

11.2.5.61 c_midi_control_mod_gmute

 $\verb|const| int seq64::c_midi_control_mod_gmute|\\$

11.2.5.62 c_midi_control_mod_glearn

```
const int seq64::c_midi_control_mod_glearn
```

11.2.5.63 c_midi_control_play_ss

```
const int seq64::c_midi_control_play_ss
```

11.2.5.64 c_midi_controls

```
const int seq64::c_midi_controls
```

11.2.5.65 c_scales_policy

```
const bool seq64::c_scales_policy[c_scale_size][SEQ64_OCTAVE_SIZE]
```

See the following sites for more information:

- http://method-behind-the-music.com/theory/scalesandkeys/
- https://en.wikipedia.org/wiki/Heptatonic_scale
- https://en.wikibooks.org/wiki/Music_Theory/Scales_and_Intervals

Note that melodic minor descends in the same way as the natural minor scale, so it descends differently than it ascends. We don't deal with that trick, at all. In the following table, the scales all start with C, but seq24/sequencer64 allow other starting notes (e.g. "keys").

```
Chromatic
                  C C# D D# E F F# G G# A A# B
                                                      Notes, chord
Major
                  С
                     . D
                           . E F
                                    . G
                                          . A
Minor
                  C . D Eb .
                                 F
                                    . G Ab .
                                               Bb .
Harmonic Minor C . D
Melodic Minor C . D
C Whole Tone C . D
                            Eb .
                                 F
                                       G
                                         Ab .
                     . D Eb .
                                                      Descending diff.
                                 F
                                       G
                                          . A
                                                  В
                            . E
                                    F# .
                                          G# . A# .
                                                      C+7 chord
                  C . .
C . D
Blues
                           Eb .
                                 F
                                    Gb G
                                               Bb .
                                          . .
Major Pentatonic C
                                    . G
                           . E
Minor Pentatonic C . . Eb .
                                 F
                                            . Bb .
                                    . G .
Octatonic 1 C . D Eb . Octatonic 2 C Db . Eb E
                                 F
                                    Gb . Ab A . B
                                                      Unimplemented
                           Eb E F F# G
                                          . A Bb .
                                                      Unimplemented
```

11.2.5.66 c_scales_transpose_up

```
const int seq64::c_scales_transpose_up[c_scale_size][SEQ64_OCTAVE_SIZE]
```

For example, if we simply add 1 semitone to each note, it remains a minor key, but it is in a different minor key. Using the transpositions in these arrays, the minor key remains the same minor key.

Minor Transpose up Result up	C 2 D	0	D 1 D#	D# 2 F	0	F 2 G	0	G 1 G#	2	0	A# 2 C	0
Harmonic minor Transpose up Result up	C 2 D		D 1 Eb	Eb 2 F		F 2 G		G 1 Ab	Ab 3 B			B 1 C
Melodic minor Transpose up Result up	C 2 D		D 1 Eb	Eb 2 F		F 2 G	:	G 2 A		A 2 B		B 1 C
C Whole Tone Transpose up Result up	C 2 D	· ·	D 2 E		E 2 F#		2		2			
Blues Transpose up Result up	C 3 Eb			Eb 2 F		F 1 Gb	Gb 1 G	G 3 Bb			2	
Major Pentatonic Transpose up Result up	C 2 D		D 2 E	· ·	E 3 G							
Minor Pentatonic Transpose up Result up	C 3 Eb			Eb 2 F		F 2 G		G 3 Bb			Bb 2 C	

11.2.5.67 c scales transpose dn

const int seq64::c_scales_transpose_dn[c_scale_size][SEQ64_OCTAVE_SIZE]

```
C . D . E F . G . A . B
Major
Transpose down
                       1
                           . 2
                                  .
                                      2 1
                                                2
                                                       2
                                                               2
Result down
                       C . D D# . F . G G# . A# .
Minor
                   2 . 2 1 . 2 . 2 1 . 2
Transpose down
                       A# . C D . D# . F G . G# .
Result down

      Harmonic minor
      C
      . D
      Eb
      . F
      . G
      Ab
      . B

      Transpose down
      1
      . 2
      1
      . 2
      . 2
      . 2
      . 3

      Result down
      B
      . C
      D
      . Eb
      . F
      G
      . At

Melodic minor
                  C
1
                       C . D Eb . F
                                             . G
                           . 2 1 . 2 . 2
Transpose down
                       B . C D . Eb . F . G . A
Result down
C whole tone
                       C . D . E . F# . G# . A# .
                                         . 2 . 2 . 2
. E . F# . G#
Transpose down
                       2 . 2 . 2
Result down
                       A# .
                              С
                                  . D
                       C . . Eb . F Gb G . . Bb . 2 . 3 . 2 1 1 . . 3 .
Blues

      Transpose down
      2 . . 3 . 2 1 1 . . 3 .

      Result down
      Bb . . C . Eb F Gb . . G .

Major Pentatonic \, C \, D \, E \, . \, G \, A \, .
Transpose down
                                         . . 3 . 2
                      3 . 2 . 2
                       A . C . D . . E . G
Result down
Transpose down 2 . . 3 . 2 . 2
Result down Bb . . C . Eb . F
```

```
11.2.5.68  c_scales_text
const char seq64::c_scales_text[c_scale_size][20]

11.2.5.69  c_key_text

const char seq64::c_key_text[SEQ64_OCTAVE_SIZE][4]

11.2.5.70  c_interval_text

const char seq64::c_interval_text[16][4]

11.2.5.71  c_chord_text
```

However, we have not seen this menu in the GUI! Ah, it only appears if the user has selected a musical scale like Major or Minor.

```
11.2.5.72 c_chord_number
const int seq64::c_chord_number
```

const char seq64::c_chord_text[8][6]

The chord-number is a count of the number of entries in c_chord_table_text. Will never change, luckily.

```
11.2.5.73  c_chord_table_text
const char seq64::c_chord_table_text[c_chord_number][12]
```

These chords appear in the sequence-editor chord-button dropdown menu. The longest string is 11 characters, and we add one for the null terminator. A good case for using std::string here. :-)

```
11.2.5.74   c_chord_size

const int seq64::c_chord_size

11.2.5.75   c_chord_table

const int seq64::c_chord_table[c_chord_number][c_chord_size]
```

These values indicate the note offsets needed for a particular kind of chord. 0 means no offset, and a -1 ends the list of note offsets for the chord.

```
11.2.5.76 c_max_instruments
```

```
const int seq64::c_max_instruments
```

With a value of 64, this is more of a sanity-check than a realistic number of instruments defined by a user.

11.2.5.77 c_max_busses

```
const int seq64::c_max_busses
```

11.2.5.78 versiontext

```
const std::string seq64::versiontext [static]
```

This value ultimately comes from the configure.ac script.

This was too redundant:

```
SEQ64_PACKAGE " " SEQ64_VERSION " (" SEQ64_GIT_VERSION ") " DATE "\n"
```

11.2.5.79 long_options

```
struct option seq64::long_options[] [static]
```

Note the terminating null structure..

```
11.2.5.80 s_arg_list
```

```
const std::string seq64::s_arg_list [static]
```

The following string keeps track of the characters used so far. An 'x' means the character is used; an 'o' means it is used for the legacy spelling of the option, which uses underscores instead of hyphens. An 'a' indicates we could repurpose the key with minimal impact.

Previous arg-list, items missing! "ChVH:lRrb:q:Lni:jJmaAM:pPusSU:x:"

11.2.5.81 s_help_1a

```
const char* const seq64::s_help_la [static]
```

11.2.5.82 s_help_1b

```
const char* const seq64::s_help_1b [static]
```

```
11.2.5.83 s_help_2
const char* const seq64::s_help_2 [static]
11.2.5.84 s_help_3
const char* const seq64::s_help_3 [static]
11.2.5.85 s_help_4
const char* const seq64::s_help_4 [static]
11.2.5.86 s_build_highlight_empty
const std::string seq64::s_build_highlight_empty [static]
11.2.5.87 s_build_lash_support
const std::string seq64::s_build_lash_support [static]
11.2.5.88 s_build_jack_support
const std::string seq64::s_build_jack_support [static]
11.2.5.89 s_build_jack_session
const std::string seq64::s_build_jack_session [static]
11.2.5.90 s_event_editor
const std::string seq64::s_event_editor [static]
11.2.5.91 s_build_pause_support
const std::string seq64::s_build_pause_support [static]
11.2.5.92 s_build_use_event_map
const std::string seq64::s_build_use_event_map [static]
```

```
11.2.5.93 s_build_chord_generator
const std::string seq64::s_build_chord_generator [static]
11.2.5.94 s_build_edit_highlight
const std::string seq64::s_build_edit_highlight [static]
11.2.5.95 s_build_timesig_tempo
const std::string seq64::s_build_timesig_tempo [static]
11.2.5.96 s_build_midi_vector
const std::string seq64::s_build_midi_vector [static]
11.2.5.97 s build solid grid
const std::string seq64::s_build_solid_grid [static]
11.2.5.98 s_build_follow_progress
const std::string seq64::s_build_follow_progress [static]
11.2.5.99 s_statistics_support
const std::string seq64::s_statistics_support [static]
11.2.5.100 s_strip_empty_mutes
const std::string seq64::s_strip_empty_mutes [static]
11.2.5.101 s_seq32_jack_support
const std::string seq64::s_seq32_jack_support [static]
11.2.5.102 s_seq32_transport
const std::string seq64::s_seq32_transport [static]
```

11.2.5.103 s_seq32_transpose

```
const std::string seq64::s_seq32_transpose [static]
```

11.2.5.104 s_seq32_menu_buttons

```
const std::string seq64::s_seq32_menu_buttons [static]
```

11.2.5.105 s_character_mapping

```
struct charpair_t seq64::s_character_mapping[]
```

11.2.5.106 s_global_lash_driver

```
lash* seq64::s_global_lash_driver [static]
```

It is actually hidden in this module now, so that a function can be used in its place.

Like the font renderer, This item was once created in the main module, sequencer64.cpp. Now we make it a safer, more fool-proof, function. However, unlike the font-render, which always exists, the LASH driver is conditional, and might not be wanted. Therefore, we cannot return a reference, because there's no such thing as a null reference in C++. We have to return a pointer.

11.2.5.107 c_status_replace

```
const int seq64::c_status_replace [static]
```

Note how they specify different bit values, as it they could be masked together to signal multiple functions.

This value signals the "replace" functionality.

11.2.5.108 c status snapshot

```
const int seq64::c_status_snapshot [static]
```

11.2.5.109 c_status_queue

```
const int seq64::c_status_queue [static]
```

11.2.5.110 g_rc_settings

```
rc_settings seq64::g_rc_settings [static]
```

```
11.2.5.111 g_user_settings
user_settings seq64::g_user_settings [static]

11.2.5.112 s_handlesize [1/2]

const long seq64::s_handlesize [static]

11.2.5.113 s_jitter_amount

const int seq64::s_jitter_amount [static]

11.2.5.114 gs_mainwid_pointer

mainwid* seq64::gs_mainwid_pointer [static]

We have decided that passing along a mainwind reference
```

We have decided that passing along a mainwnd reference among a number of constructors is too much and actually harder to understand and more error prone. This value is set at the end of the mainwnd constructor, but only the first time that constructor is called.

```
11.2.5.115  c_mainwid_x
const int seq64::c_mainwid_x
```

Affected by the c_mainwid_border and c_mainwid_spacing values.

```
11.2.5.116  c_mainwid_y

const int seq64::c_mainwid_y

11.2.5.117  gs_perfedit_pointer_0

perfedit* seq64::gs_perfedit_pointer_0  [static]

11.2.5.118  gs_perfedit_pointer_1

perfedit* seq64::gs_perfedit_pointer_1  [static]

11.2.5.119  s_handlesize [2/2]


const long seq64::s_handlesize [static]
```

Chapter 12

Data Structure Documentation

12.1 seq64::AbstractPerfInput Class Reference

Provides an abstract base class to provide the minimal interface for the various "perf input" classes. Inheritance diagram for seq64::AbstractPerfInput:



Public Member Functions

AbstractPerfInput ()

Default constructor.

Protected Member Functions

virtual ∼AbstractPerfInput ()

Destructor, does nothing.

- virtual bool on_button_press_event (GdkEventButton *a_ev, perfroll &roll)=0
- virtual bool on_button_release_event (GdkEventButton *a_ev, perfroll &roll)=0
- virtual bool on_motion_notify_event (GdkEventMotion *a_ev, perfroll &roll)=0
- virtual void activate_adding (bool adding, perfroll &roll)=0
- virtual bool handle_motion_key (bool is_left, perfroll &roll)=0
- bool is_adding () const

'Getter' function for member m_adding

void set_adding (bool flag)

'Setter' function for member m_adding

• bool is_adding_pressed () const

'Getter' function for member m_adding_pressed

void set_adding_pressed (bool flag)

'Setter' function for member m_adding_pressed

Private Attributes

· bool m_adding

Indicates we are in the middle of adding a sequence segment to the performance.

• bool m_adding_pressed

Indicates if the left mouse button is pressed while in adding mode.

Friends

class perfroll

12.1.1 Constructor & Destructor Documentation

12.1.1.1 AbstractPerfInput()

```
seq64::AbstractPerfInput::AbstractPerfInput ( ) [inline]
```

12.1.1.2 ~AbstractPerfInput()

virtual seq64::AbstractPerfInput::~AbstractPerfInput () [inline], [protected], [virtual]

12.1.2 Member Function Documentation

```
12.1.2.1 on_button_press_event()
```

Implemented in seq64::Seq24PerfInput, and seq64::FruityPerfInput.

12.1.2.2 on_button_release_event()

Implemented in seq64::Seq24PerfInput, and seq64::FruityPerfInput.

12.1.2.3 on_motion_notify_event()

Implemented in seq64::Seq24PerfInput, and seq64::FruityPerfInput.

12.1.2.4 activate_adding()

Implemented in seq64::Seq24PerfInput, and seq64::FruityPerfInput.

12.1.2.5 handle_motion_key()

Implemented in seq64::Seq24PerfInput, and seq64::FruityPerfInput.

12.1.2.6 is_adding()

```
bool seq64::AbstractPerfInput::is_adding ( ) const [inline], [protected]
```

12.1.2.7 set_adding()

```
void seq64::AbstractPerfInput::set\_adding (
             bool flag ) [inline], [protected]
12.1.2.8 is_adding_pressed()
bool seq64::AbstractPerfInput::is_adding_pressed ( ) const [inline], [protected]
```

12.1.2.9 set_adding_pressed()

```
void seq64::AbstractPerfInput::set_adding_pressed (
            bool flag ) [inline], [protected]
```

12.1.3 Friends And Related Function Documentation

12.1.3.1 perfroll

```
friend class perfroll [friend]
```

12.1.4 Field Documentation

12.1.4.1 m_adding

```
bool seq64::AbstractPerfInput::m_adding [private]
```

12.1.4.2 m_adding_pressed

```
bool seq64::AbstractPerfInput::m_adding_pressed [private]
```

12.2 seq64::automutex Class Reference

Provides a mutex that locks automatically when created, and unlocks when destroyed.

Public Member Functions

• automutex (mutex &my_mutex)

Principal constructor gets a reference to a mutex parameter, and then locks the mutex.

∼automutex ()

The destructor unlocks the mutex.

Private Member Functions

- automutex ()
- automutex (const automutex &)
- automutex & operator= (const automutex &)

Private Attributes

mutex & m_safety_mutex

Provides the mutex reference to be used for locking.

12.2.1 Detailed Description

This has a couple of benefits. First, it is threadsafe in the face of exception handling. Secondly, it can be done with just one line of code.

12.2.2 Constructor & Destructor Documentation

```
12.2.2.4 \simautomutex()
```

Parameters

my_mutex

```
seq64::automutex::\sim automutex ( ) [inline]
```

The caller's mutex to be used for locking.

12.2.3 Member Function Documentation

12.2.3.1 operator=()

12.2.4 Field Documentation

12.2.4.1 m_safety_mutex

```
mutex& seq64::automutex::m_safety_mutex [private]
```

12.3 seq64::click Class Reference

Encapsulates any possible mouse click.

Public Member Functions

• click ()

The constructor for class click.

click (int x, int y, int button=SEQ64_CLICK_BUTTON_LEFT, bool press=true, seq_modifier_t modkey=SE
 — Q64_NO_MASK)

Principal constructor for class click.

• click (const click &rhs)

Provides a stock copy constructor.

• click & operator= (const click &rhs)

Provides a stock principal assignment operator.

• bool is_press () const

'Getter' function for member m_is_press

• bool is_left () const

'Getter' function for member m button to test for the left button.

• bool is_middle () const

'Getter' function for member m_button to test for the middle button.

bool is_right () const

'Getter' function for member m_button to test for the right button.

• int x () const

'Getter' function for member m_x

• int y () const

'Getter' function for member m_y

• int button () const

'Getter' function for member m_button

• seq_modifier_t modifier () const

'Getter' function for member $m_{modifier}$

• bool mod_control () const

'Getter' function for member m_modifier tested for Ctrl key.

bool mod_control_shift () const

'Getter' function for member m modifier tested for Ctrl and Shift key.

bool mod_super () const

'Getter' function for member m_modifier tested for Mod4/Super/Windows key.

Private Attributes

• bool m_is_press

Determines if the click was a press or a release event.

• int m_x

The x-coordinate of the click.

• int m_y

The y-coordinate of the click.

• int m_button

The button that was pressed or released.

• seq_modifier_t m_modifier

The optional modifier value.

12.3.1 Detailed Description

Useful in passing more generic events to non-GUI classes.

12.3.2 Constructor & Destructor Documentation

```
12.3.2.1 click() [1/3]
seq64::click::click ( )
```

Sets all members to false, zero, or the lowest good value.

```
12.3.2.2 click() [2/3]
seq64::click::click (
    int x,
    int y,
    int button = SEQ64_CLICK_BUTTON_LEFT,
    bool press = true,
    seq_modifier_t modkey = SEQ64_NO_MASK )
```

This function is the only way to set value for the click members (other than the copy constructor and principal assignment operator.

Parameters

X	The putative x value of the button click.					
У	The putative y value of the button click.					
button	The value of the button that was clicked, set to 1, 2, or 3.					
press	Set to true if the event was a button press, false if it was a button release.					
modkey	Indicates which modifier key (such as Ctrl or Alt), if any, was pressed at the same time as the click					
	action.					

It is nice to be explicit about these kinds of functions, even if it gets tedious.

Parameters

rhs Provies the source object to be copied.

12.3.3 Member Function Documentation

12.3.3.1 operator=()

It is nice to be explicit about these kinds of functions, even if it gets tedious.

Parameters

rhs

Provies the source object to be assigned from. The assignment is not made if "this" has the same address as this parameter.

Returns

Returns a reference to self for usage in a string of assignments.

12.3.3.2 is_press()

```
bool seq64::click::is_press ( ) const [inline]

12.3.3.3 is_left()

bool seq64::click::is_left ( ) const [inline]

12.3.3.4 is_middle()

bool seq64::click::is_middle ( ) const [inline]

12.3.3.5 is_right()
```

bool seq64::click::is_right () const [inline]

```
12.3.3.6 x()
int seq64::click::x ( ) const [inline]
12.3.3.7 y()
int seq64::click::y ( ) const [inline]
12.3.3.8 button()
int seq64::click::button ( ) const [inline]
12.3.3.9 modifier()
seq_modifier_t seq64::click::modifier ( ) const [inline]
12.3.3.10 mod_control()
bool seq64::click::mod_control ( ) const [inline]
12.3.3.11 mod_control_shift()
bool seq64::click::mod_control_shift ( ) const [inline]
12.3.3.12 mod_super()
bool seq64::click::mod_super ( ) const [inline]
12.3.4 Field Documentation
12.3.4.1 m_is_press
bool seq64::click::m_is_press [private]
12.3.4.2 m_x
int seq64::click::m_x [private]
0 is the left-most coordinate.
```

12.3.4.3 m_y

```
int seq64::click::m_y [private]
```

0 is the top-most coordinate.

12.3.4.4 m_button

```
int seq64::click::m_button [private]
```

Left is 1, mmiddle is 2, and right is 3. These numbers are defined via macros, and are Linux-specific and Gtk-specific.

12.3.4.5 m_modifier


```
seq_modifier_t seq64::click::m_modifier [private]
```

Note that SEQ64_NO_MASK is our word for 0, meaning "no modifier".

12.4 seq64::condition_var Class Reference

A mutex works best in conjunction with a condition variable.

Inheritance diagram for seq64::condition_var:



Public Member Functions

• condition_var ()

Initialize the condition variable with the global variable.

• void wait ()

Waits for the condition variable.

• void signal ()

Signals the condition variable.

Private Attributes

• pthread_cond_t m_cond

Provides a class-specific condition variable.

Static Private Attributes

static const pthread_cond_t sm_cond
 Provides a "global" condition variable.

Additional Inherited Members

12.4.1 Detailed Description

Therefore this class derives from the mutex class. A "has-a" relationship might be more logical than this "is-a" relationship.

12.4.2 Constructor & Destructor Documentation

```
12.4.2.1 condition_var()
```

```
seq64::condition_var::condition_var ( )
```

12.4.3 Member Function Documentation

```
12.4.3.1 wait()
```

```
void seq64::condition_var::wait ( )
```

12.4.3.2 signal()

```
void seq64::condition_var::signal ( )
```

12.4.4 Field Documentation

12.4.4.1 sm_cond

```
const pthread_cond_t seq64::condition_var::sm_cond [static], [private]
```

Define the static condition variable used by all mutex locks.


12.4.4.2 m_cond

```
pthread_cond_t seq64::condition_var::m_cond [private]
```

12.5 seq64::configfile Class Reference

This class is the abstract base class for optionsfile and userfile.

Inheritance diagram for seq64::configfile:



Public Member Functions

• configfile (const std::string &name)

Provides the string constructor for a configuration file.

virtual ∼configfile ()

A rote destructor needed for a base class.

- virtual bool parse (perform &perf)=0
- virtual bool write (const perform &perf)=0

Protected Member Functions

bool next_data_line (std::ifstream &file)

Gets the next line of data from an input stream.

bool line_after (std::ifstream &file, const std::string &tag)

This function gets a specific line of text, specified as a tag.

Protected Attributes

· std::string m_name

Provides the name of the configuration file.

• char * m d

Points to an allocated buffer that holds the data for the configuration file.

char m_line [SEQ64_LINE_MAX]

The current line of text being processed.

12.5.1 Constructor & Destructor Documentation

12.5.1.1 configfile()

Parameters

name The name of the configuration file.

12.5.1.2 \sim configfile()

```
\label{lem:configfile::} virtual \ seq64{::} configfile{::} \sim configfile \ (\ ) \quad [inline] \mbox{, [virtual]}
```

12.5.2 Member Function Documentation

12.5.2.1 next_data_line()

If the line starts with a number-sign, a space (!), or a null, it is skipped, to try the next line. This occurs until an EOF is encountered.

Member m_line is a "global" return value.

Parameters

file

Points to an input stream. We converted this item to a reference; pointers can be subject to problems. For example, what if someone passes a null pointer?

Returns

Returns true if a presumed data line was found. False is returned if not found before an EOF or a section marker ("[") is found. This is a a new (ca 2016-02-14) feature of this function, to assist in adding new data to the file.

12.5.2.2 line_after()

Then it gets the next non-blank line (i.e. data line) after that.

This function always starts from the beginning of the file. Therefore, it can handle reading Sequencer64 configuration files that have had their tagged sections arranged in a different order. This feature makes the configuration file a little more robust against errors.

Parameters

file	Points to the input file stream.
tag	Provides a tag to be found. Lines are read until a match occurs with this tag. Normally, the tag is a
	section marker, such as "[user-interface]". Best to assume an exact match is needed.

Returns

Returns true if the tag was found. Otherwise, false is returned.

12.5.2.3 parse()

Implemented in seq64::optionsfile, and seq64::userfile.

12.5.2.4 write()

Implemented in seq64::optionsfile, and seq64::userfile.

12.5.3 Field Documentation

12.5.3.1 m_name

std::string seq64::configfile::m_name [protected]

12.5.3.2 m_d

char* seq64::configfile::m_d [protected]

12.5.3.3 m_line


char seq64::configfile::m_line[SEQ64_LINE_MAX] [protected]

This member receives an input line, and so needs to be a character buffer.

12.6 seq64::editable_event Class Reference

Provides for the management of MIDI editable events.

Inheritance diagram for seq64::editable_event:



Data Structures

· struct name value t

Provides a type that contains the pair of values needed for the various lookup maps that are needed to manage editable events.

Public Types

```
    enum category_t {
        category_name,
        category_channel_message,
        category_system_message,
        category_meta_event,
        category_prop_event }
```

These values determine the major kind of event, which determines what types of events are possible for this editable event object.

```
    enum timestamp_format_t {
        timestamp_measures,
        timestamp_time,
        timestamp_pulses }
```

Provides a code to indicate the desired timestamp format.

Public Member Functions

• editable event (const editable events &parent)

This constructor simply initializes all of the class members.

editable_event (const editable_events &parent, const event &ev)

Event constructor.

editable_event (const editable_event &rhs)

This copy constructor initializes most of the class members.

- editable_event & operator= (const editable_event &rhs)
- virtual ∼editable_event ()

This destructor current is a rote virtual function override.

const editable_events & parent () const

'Getter' function for member m parent

· category_t category () const

'Getter' function for member m_category

void category (category_t c)

'Setter' function for member m category by value Also keeps the m name category member in synchrony.

· const std::string & category_string () const

'Getter' function for member m_category

void category (const std::string &cs)

'Setter' function for member m_category by name Also keeps the m_name_category member in synchrony, but looks up the name, rather than using the name parameter, to avoid storing abbreviations.

const std::string & timestamp_string () const

'Getter' function for member m_name_timestamp

· midipulse timestamp () const

'Getter' function for member event::get_timestamp() Implemented to allow a uniform naming convention that is not slavish to the get/set crowd [this ain't Java].

· void timestamp (midipulse ts)

'Setter' function for member event::set_timestamp() Implemented to allow a uniform naming convention that is not slavish to the get/set crowd [this ain't Java].

void timestamp (const std::string &ts string)

'Setter' function for member event::set_timestamp() [string version]

std::string time_as_pulses ()

Converts the current time-stamp to a string representation in units of pulses.

• std::string time as measures ()

Converts the current time-stamp to a string representation in units of measures, beats, and divisions.

std::string time_as_minutes ()

Converts the current time-stamp to a string representation in units of hours, minutes, seconds, and fraction.

void set_status_from_string (const std::string &ts, const std::string &ts, con

Converts a string into an event status, along with timestamp and data bytes.

• std::string format_timestamp ()

Formats the current timestamp member as a string.

• std::string stock_event_string ()

Converts the event into a string desribing the full event.

• std::string status_string () const

'Getter' function for member m_name_status

• std::string meta_string () const

'Getter' function for member m_name_meta

std::string seqspec_string () const

'Getter' function for member m_name_seqspec

std::string channel_string () const

'Getter' function for member m name channel

std::string data_string () const

'Getter' function for member m_name_data

Static Public Member Functions

static std::string value_to_name (midibyte value, category_t cat)

Provides a static lookup function that returns the name, if any, associated with a midibyte value.

static unsigned short name_to_value (const std::string &name, category_t cat)

Provides a static lookup function that returns the value, if any, associated with a name string.

Static Public Attributes

static const name_value_t sm_category_names []

An array of event categories and their names.

static const name_value_t sm_channel_event_names []

An array of MIDI channel events and their names.

• static const name_value_t sm_system_event_names []

An array of MIDI system events and their names.

static const name_value_t sm_meta_event_names []

An array of Meta events and their names.

static const name_value_t sm_prop_event_names[]

An array of Sequencer64-specific events and their names.

static const name_value_t *const sm_category_arrays[]

Provides for fast access (no ifs) to the correct name array for the given category.

Private Member Functions

- editable_event ()
- void analyze ()

Analyzes an editable-event to make all the settings it needs.

Private Attributes

· const editable_events & m_parent

Provides a reference to the container that holds this event.

category_t m_category

Indicates the overall category of this event, which will be category_channel_message, category_system_message, category_meta_event, and category_prop_event.

• std::string m_name_category

Holds the name of the event category for this event.

timestamp_format_t m_format_timestamp

Indicates the format to display the time-stamp.

std::string m name timestamp

Holds the string version of the MIDI pulses time-stamp.

std::string m name status

Holds the name of the status value for this event.

• std::string m name meta

Holds the name of the meta message, if applicable.

std::string m_name_seqspec

If we eventually implement the editing of the Seq24/Sequencer64 "proprietary" meta sequencer-specific events, the name of the SeqSpec will be stored here.

std::string m name channel

Holds the channel description, if applicable.

• std::string m_name_data

Holds the data description, if applicable.

12.6.1 Detailed Description

It makes the following members of an event modifiable using human-readable strings:

- m_timestamp
- m_status
- m_channel
- m_data[]

Eventually, it would be nice to be able to edit, or at least view, the SysEx events and the Meta events. Those two will require extensions to make events out of them (SysEx is partly supported).

To the concepts of event, the editable_event class adds a category field and strings to represent all of these members.

12.6.2 Member Enumeration Documentation

12.6.2.1 category_t

```
enum seq64::editable_event::category_t
```

These tags are accompanied by category names in sm_category_names[]. The enum values are cast to midibyte values for the purposes of using the lookup infrastructure.

Enumerator

category_name	Indicates that the lookup needs to be done on the category names, as listed in sm_category_names[].
category_channel_message	Indicates a channel event, with a value ranging from 0x80 through 0xEF. Some examples are note on/off, control change, and program change. Values are looked up in sm_channel_event_names[].
category_system_message	Indicates a system event, with a value ranging from 0xF0 through 0xFF. Some examples are SysEx start/end, song position, and stop/start/continue/reset. Values are looked up in sm_system_event_names[].
category_meta_event	Indicates a meta event, and there is a second value that is used to look up the name of the meta event, in sm_meta_event_names[].
category_prop_event	Indicates a "proprietary", Sequencer64 event. Indicates to look up the name of the event in sm_prop_event_names[]. Not sure if these kinds of events will be stored separately.

12.6.2.2 timestamp_format_t

```
enum seq64::editable_event::timestamp_format_t
```

Three are supported. All editable events will share the same timestamp format, but it seems good to make this a event class member, rather than something imposed from an outside static value. We shall see.

Enumerator

timestamp_measures	This format displays the time in "measures:beats:divisions" format, where measures and beats start at 1. Thus, "1:1:0" is equivalent to 0 pulses or to "0:0:0:0.0" in normal time values.
timestamp_time	This format displays the time in "hh:mm:second.fraction" format. The value displayed should not depend upon the internal timing parameters of the event.
timestamp_pulses	This format specifies a bare pulse format for the timestamp – a long integer ranging from 0 on up. Obviously, this representation depends on the PPQN value for the sequence holding this event.

12.6.3 Constructor & Destructor Documentation

editable_event::editable_event (): event (), m_category (category_name), m_name_category (), m_format_
timestamp (timestamp_measures), m_name_timestamp (), m_name_status (), m_name_meta (), m_name_
seqspec (), m_name_channel (), m_name_data () { // Empty body } Principal constructor.

Parameters

This function basically adds all of the extra editable_event stuff to a standard event, so that the resulting editable ← event is container-ready.

This function is currently geared only toward support of the SMF 0 channel-splitting feature. Many of the members are not set to useful values when the MIDI file is read, so we don't handle them for now.

Warning

This function does not yet copy the SysEx data. The inclusion of SysEx editable_events was not complete in Seq24, and it is still not complete in Sequencer64. Nor does it currently bother with the links.

Parameters

rhs Provides the editable_event object to be copied.

```
12.6.3.5 \simeditable_event()
```

```
virtual seq64::editable_event::~editable_event ( ) [inline], [virtual]
```

12.6.4 Member Function Documentation

12.6.4.1 value_to_name()

Parameters

value	The MIDI byte value to look up.
cat	The category of the MIDI byte. Each category calls a different name array into play.

Returns

Returns the name associated with the value. If there is no such name, then an empty string is returned.

12.6.4.2 name_to_value()

The string_match() function, which can match abbreviations, case-insensitively, is used to make the string comparisons.

Parameters

ſ	name	The string value to look up.
	cat	The category of the MIDI byte. Each category calls a different name array into play.

Returns

Returns the value associated with the name. If there is no such value, then SEQ64_END_OF_MIDIBYTE_← TABLE is returned.

12.6.4.3 operator=()

Note that a bad value is translated to the value of category_name.

Parameters

c Provides the category value to set.

12.6.4.7 category_string()

Note that a bad value is translated to the value of category_name.

Parameters

name Provides the category name for the category value to set.

12.6.4.9 timestamp_string()

Plus, we also have to set the string version at the same time.

The format of the string representation is of the format selected by the m_format_timestamp member and is set by the format_timestamp() function.

Parameters

ts | Provides the timestamp in units of MIDI pulses.

```
12.6.4.12 timestamp() [3/3]
void seq64::editable_event::timestamp (
```

const std::string & ts_string)

The format of the string representation is of the format selected by the m_format_timestamp member and is set by the format_timestamp() function.

Parameters

ts_string Provides the timestamp in units of MIDI pulses.	ts string P
---	-------------

12.6.4.13 time_as_pulses() std::string seq64::editable_event::time_as_pulses () [inline]

12.6.4.14 time_as_measures()

```
{\tt std::string seq64::editable\_event::time\_as\_measures} ( )
```

Cannot be inlined because of a circular dependency between the editable_event and editable_events classes.

12.6.4.15 time_as_minutes()

```
std::string seq64::editable_event::time_as_minutes ( )
```

Cannot be inlined because of a circular dependency between the editable_event and editable_events classes.

12.6.4.16 set_status_from_string()

```
void seq64::editable_event::set_status_from_string ( const std::string & ts, const std::string & s, const std::string & sd0, const std::string & sd1)
```

Currently, this function handles only the following two messages:

- · category_channel_message
- · category_system_message

After all of the numbering member items have been set, they are converted and assigned to the string versions via a call to the analyze() function.

Parameters

ts	Provides the time-stamp string of the event.
s	Provides the name of the event, such as "Program Change".
sd0	Provides the string defining the first data byte of the event.
sd1	Provides the string defining the second data byte of the event, if applicable to the event.

12.6.4.17 format_timestamp()

```
std::string seq64::editable_event::format_timestamp ( )
```

The format of the string representation is of the format selected by the m_format_timestamp member.

12.6.4.18 stock_event_string()

```
std::string seq64::editable_event::stock_event_string ( )
```

We get the time-stamp as a string, make sure the event is fully analyzed so that all items and strings are set correctly.

Returns

Returns a human-readable string describing this event.

12.6.4.19 status_string()

```
std::string seq64::editable_event::status_string ( ) const [inline]
```

12.6.4.20 meta_string()

```
std::string seq64::editable_event::meta_string ( ) const [inline]
```

12.6.4.21 seqspec_string()

```
std::string seq64::editable_event::seqspec_string ( ) const [inline]
```

12.6.4.22 channel_string()

```
std::string seq64::editable_event::channel_string ( ) const [inline]
```

12.6.4.23 data_string()

```
std::string seq64::editable_event::data_string ( ) const [inline]
```

12.6.4.24 analyze()

```
void seq64::editable_event::analyze ( ) [private]
```

Used in the constructors. Some of the setters indirectly set the appropriate string representation, as well.

Category:

```
This function can figure out if the status byte implies a channel message or a system message, and set the category string as well. However, at this time, detection of Meta events (0xFF) or Proprietary/SeqSpec events (0xFF with 0x2424) doesn't work due to lack of context here (and due to the fact that currently such events are not yet stored in a Sequencer64 sequence/track, and the least-significant-byte gets masked off anyway.)
```

Status:

We distinguish between channel and system messages, and then one— and two-byte messages, but don't yet distinguish the data values fully.

12.6.5 Field Documentation

12.6.5.1 sm_category_names

```
const editable_event::name_value_t seq64::editable_event::sm_category_names [static]
```

Initializes the array of event/name pairs for the MIDI events categories.

Terminated by an empty string, the latter being the preferred test, for consistency with the other arrays and because 0 is often a legitimate code value.

12.6.5.2 sm_channel_event_names

```
const editable_event::name_value_t seq64::editable_event::sm_channel_event_names [static]
```

Initializes the array of event/name pairs for the channel MIDI events.

We split channel and system messages into two arrays, for semantic reasons and for faster linear lookups.

Terminated by an empty string.

12.6.5.3 sm_system_event_names

```
const editable_event::name_value_t seq64::editable_event::sm_system_event_names [static]
```

Initializes the array of event/name pairs for the system MIDI events.

We split channel and system messages into two arrays, for semantic reasons and for faster linear lookups.

Terminated by an empty string.

```
12.6.5.4 sm_meta_event_names
```

```
const editable_event::name_value_t seq64::editable_event::sm_meta_event_names [static]
```

Initializes the array of event/name pairs for all of the Meta events.

Terminated only by the empty string.

12.6.5.5 sm_prop_event_names

```
const editable_event::name_value_t seq64::editable_event::sm_prop_event_names [static]
```

Initializes the array of event/name pairs for all of the seq24/sequencer64-specific events.

Terminated only by the empty string. Note that the numbers reflect the masking off of the high-order bits by 0x242400FF.

12.6.5.6 sm_category_arrays

```
const editable_event::name_value_t *const seq64::editable_event::sm_category_arrays [static]
```

Contains pointers (references cannot be stored in an array) to the desired array for a given category.

Too bad that an array of references is not possible.

This code could be considered a bit rococo.

12.6.5.7 m_parent

```
const editable_events& seq64::editable_event::m_parent [private]
```

The container's "children" need to go to their "parent" to get certain items of information.

12.6.5.8 m_category

```
category_t seq64::editable_event::m_category [private]
```

The category_name value is not set here, since that category is used only for looking up the human-readable form of the category.

12.6.5.9 m_name_category

```
std::string seq64::editable_event::m_name_category [private]
```

12.6.5.10 m_format_timestamp

```
timestamp_format_t seq64::editable_event::m_format_timestamp [private]
```

The default is to display in timestamp_measures format.

12.6.5.11 m_name_timestamp

```
std::string seq64::editable_event::m_name_timestamp [private]
```

12.6.5.12 m_name_status

```
std::string seq64::editable_event::m_name_status [private]
```

It will include the names of the channel messages and the system messages. The latter includes SysEx and Meta messages.

12.6.5.13 m_name_meta

```
std::string seq64::editable_event::m_name_meta [private]
```

If not applicable, this name will be empty.

12.6.5.14 m_name_seqspec

```
std::string seq64::editable_event::m_name_seqspec [private]
```

12.6.5.15 m_name_channel

```
std::string seq64::editable_event::m_name_channel [private]
```

12.6.5.16 m name data

```
std::string seq64::editable_event::m_name_data [private]
```

12.7 seq64::editable_events Class Reference

Provides for the management of an ordered collection MIDI editable events.

Public Member Functions

editable_events (sequence &seq, int bpm)

This constructor hooks into the sequence object.

editable_events (const editable_events &rhs)

This copy constructor initializes most of the class members.

editable_events & operator= (const editable_events &rhs)

This principal assignment operator sets most of the class members.

virtual ~editable_events ()

This destructor current is a rote virtual function override.

const midi_timing & timing () const

'Getter' function for member m_midi_parameters

midipulse string_to_pulses (const std::string &ts_string) const

Calculates the MIDI pulses (divisions) from a string using one of the free functions of the calculations module.

• bool load events ()

Accesses the sequence's event-list, iterating through it from beginning to end, wrapping each event in the list in an editable event and inserting it into the editable-event container.

• bool save events ()

Erases the sequence's event container and recreates it using the edited container of editable events.

· Events & events ()

'Getter' function for member m_events

· iterator begin ()

'Getter' function for member m_events.begin(), non-constant version.

· const_iterator begin () const

'Getter' function for member m_events.begin(), constant version.

· iterator end ()

'Getter' function for member m_events.end(), non-constant version.

· const_iterator end () const

'Getter' function for member m_events.end(), constant version.

int count () const

Returns the number of events stored in m events.

• bool add (const event &e)

Adds an event, converted to an editable_event, to the internal event list.

bool add (const editable_event &e)

Adds an editable event to the internal event list.

• bool replace (iterator ie, const editable_event &e)

Provides a wrapper for the iterator form of erase(), which is the only one that the editable_events container uses.

• void remove (iterator ie)

Provides a wrapper for the iterator form of erase(), which is the only one that sequence uses.

• void clear ()

Provides a wrapper for clear().

iterator current_event () const

'Getter' function for member m_current_event The caller must make sure the iterator is not Events::end().

Static Public Member Functions

• static editable_event & dref (iterator ie)

Dereference access for list or map.

static const editable_event & dref (const_iterator ie)

Dereference const access for list or map.

Private Types

- typedef event_list::event_key Key
 - Types to use to with the multimap implementation.
- typedef std::pair< Key, editable_event > EventsPair
- typedef std::multimap< Key, editable_event > Events
- typedef std::multimap< Key, editable_event >::iterator iterator
- typedef std::multimap< Key, editable_event >::const_iterator const_iterator

Private Member Functions

- editable_events ()
- void current_event (iterator cei)

'Setter' function for member m_current_event

Private Attributes

· Events m events

Holds the editable_events.

iterator m_current_event

Points to the current event, which is the event that has just been inserted.

• sequence & m sequence

Provides a reference to the sequence containing the events to be edited.

· midi_timing m_midi_parameters

Holds the current settings for the sequence (and usually for the whole MIDI tune as well).

Friends

· class eventslots

12.7.1 Member Typedef Documentation

```
12.7.1.1 Key
```

```
typedef event_list::event_key seq64::editable_events::Key [private]
```

These typenames are identical to those used in event_list, but of course they are in the editable_events scope instead. See the event_list class.

12.7.1.2 EventsPair

```
typedef std::pair<Key, editable_event> seq64::editable_events::EventsPair [private]
```

12.7.1.3 Events

typedef std::multimap<Key, editable_event> seq64::editable_events::Events [private]

12.7.1.4 iterator

```
typedef std::multimap<Key, editable_event>::iterator seq64::editable_events::iterator [private]
```

12.7.1.5 const iterator

```
\label{typedef} $$td::multimap<Key, editable\_event>::const\_iterator seq64::editable\_events::const\_\leftrightarrow iterator [private]
```

12.7.2 Constructor & Destructor Documentation

Parameters

seq	Provides a reference to the sequence object, which provides the events and some of the MIDI timing parameters.
bpm	Provides the beats/minute value, which the caller figures out how to get and provides in this parameter.

12.7.2.3 editable_events() [3/3]

int bpm)

Note that we need to reconstitute the event links here, as well.

Parameters

rhs Provides the editable_events object to be copied.

12.7.2.4 \sim editable_events()

```
\label{lem:virtual} \verb| seq64::editable_events:: \sim \verb| editable_events ( ) [inline], [virtual] |
```

12.7.3 Member Function Documentation

12.7.3.1 operator=()

Note that we need to reconstitute the event links here, as well.

Parameters

rhs Provides the editable_events object to be assigned.

Returns

Returns a reference to "this" object, to support the serial assignment of editable_eventss.

12.7.3.2 timing()

Note that the new events will not have valid links (actually, no links). These links are used for associating Note Off events with their respective Note On events. To be consistent, we must take the time to reconstitute these links, using event list::verify and link().

Returns

Returns true if the size of the final editable_event container matches the size of the original events container.

12.7.3.5 save_events()

```
bool seq64::editable_events::save_events ( )
```

bool seq64::editable_events::load_events ()

Note that the old events are replaced only if the container of editable events is not empty. There are safer ways for the user to erase all the events.

Todo Consider what to do about the sequence::m is modified flag.

Returns

Returns true if the size of the final event container matches the size of the original editable_events container.

```
12.7.3.6 events()
Events& seq64::editable_events::events ( ) [inline]
12.7.3.7 begin() [1/2]
iterator seq64::editable_events::begin ( ) [inline]
12.7.3.8 begin() [2/2]
const_iterator seq64::editable_events::begin ( ) const [inline]
12.7.3.9 end() [1/2]
iterator seq64::editable_events::end ( ) [inline]
12.7.3.10 end() [2/2]
const_iterator seq64::editable_events::end ( ) const [inline]
12.7.3.11 dref() [1/2]
static editable_event& seq64::editable_events::dref (
             iterator ie ) [inline], [static]
Parameters
     Provides the iterator to the event to which to get a reference.
12.7.3.12 dref() [2/2]
static const editable_event& seq64::editable_events::dref (
             const_iterator ie ) [inline], [static]
Parameters
     Provides the iterator to the event to which to get a reference.
12.7.3.13 count()
int seq64::editable_events::count ( ) const [inline]
We like returning an integer instead of size_t, and rename the function so nobody is fooled.
```

e Provides the regular event to be added to the list of editable events.

Returns

Returns true if the insertion succeeded, as evidenced by an increment in container size.

For the std::multimap implementation, This is an option if we want to make sure the insertion succeed.

```
std::pair<Events::iterator, bool> result = m_events.insert(p);
return result.second;
```

Parameters

e Provides the regular event to be added to the list of editable events.

Returns

Returns true if the insertion succeeded, as evidenced by an increment in container size.

Side-effect(s) Sets m_current_event, which can be used right-away in a single-threaded context to get an iterator to the event via the current_event() accessor.

12.7.3.16 replace()

```
void seq64::editable_events::clear ( ) [inline]
```

```
12.7.3.19 current_event() [1/2]
iterator seq64::editable_events::current_event ( ) const [inline]
12.7.3.20 current_event() [2/2]
void seq64::editable_events::current_event (
             iterator cei ) [inline], [private]
```

cei Provide an iterator to the event to set as the current event.

12.7.4 Friends And Related Function Documentation

12.7.4.1 eventslots

```
friend class eventslots [friend]
```

12.7.5 Field Documentation

12.7.5.1 m_events

```
Events seq64::editable_events::m_events [private]
```

12.7.5.2 m current event

```
iterator seq64::editable_events::m_current_event [private]
```

(From this event we can get the current time and other parameters.) If the container were a plain map, we could instead use a key to access it. But we can at least use an iterator, rather than a bare pointer.

12.7.5.3 m_sequence

```
sequence& seq64::editable_events::m_sequence [private]
```

Besides the events, this object also holds the beats/measure, beat-width, and the PPQN value. The beats/minute have to be obtained from the application's perform object, and passed to the editable_events constructor by the caller.

12.7.5.4 m_midi_parameters


```
midi_timing seq64::editable_events::m_midi_parameters [private]
```

It holds the beats/minute, beats/measure, beat-width, and PPQN values needed to properly convert MIDI pulse timestamps to time and measure values.

12.8 seq64::event Class Reference

Provides events for management of MIDI events.

Inheritance diagram for seq64::event:



Public Types

typedef std::vector < midibyte > SysexContainer
 Provides a type definition for a vector of midibytes.

Public Member Functions

• event ()

This constructor simply initializes all of the class members.

• event (const event &rhs)

This copy constructor initializes most of the class members.

event & operator= (const event &rhs)

This principal assignment operator sets most of the class members.

virtual ~event ()

This destructor explicitly deletes m_sysex and sets it to null.

bool operator< (const event &rhsevent) const

If the current timestamp equal the event's timestamp, then this function returns true if the current rank is less than the event's rank.

void set timestamp (midipulse time)

'Setter' function for member m_timestamp

• midipulse get_timestamp () const

'Getter' function for member m timestamp

• midibyte get_channel () const

'Getter' function for member m_channel

· bool check_channel (int channel) const

Checks the channel number to see if the event's channel matches it, or if the event has no channel.

void mod_timestamp (midipulse modtick)

Calculates the value of the current timestamp modulo the given parameter.

• void set_status (midibyte status)

Sets the m_status member to the value of status.

void set_status (midibyte eventcode, midibyte channel)

This overload is useful when synthesizing events, such as converting a Note On event with a velocity of zero to a Note Off event

void set_status_keep_channel (midibyte eventcode)

This function is used in recording to preserve the input channel information for deciding what to do with an incoming MIDI event.

void set_channel (midibyte channel)

Sets the channel "nybble", without modifying the status "nybble".

midibyte get_status () const

'Getter' function for member m_status

void set_data (midibyte d1)

Clears the most-significant-bit of the d1 parameter, and sets it into the first byte of m_data.

void set_data (midibyte d1, midibyte d2)

 ${\it Clears the most-significant-bit of both parameters, and sets them into the first and second bytes of {\it m_data}.}$

void get_data (midibyte &d0, midibyte &d1) const

Retrieves the two data bytes from m_data[] and copies each into its respective parameter.

void increment_data1 ()

Increments the first data byte (m_data[0]) and clears the most significant bit.

void decrement_data1 ()

Decrements the first data byte (m_data[0]) and clears the most significant bit.

void increment_data2 ()

Increments the second data byte (m_data[1]) and clears the most significant bit.

void decrement_data2 ()

Decrements the second data byte (m_data[1]) and clears the most significant bit.

bool append sysex (midibyte *data, int len)

Appends SYSEX data to a new buffer.

bool append_sysex (midibyte data)

An overload for obtaining SYSEX data byte-by-byte.

void restart_sysex ()

Deletes and clears out the SYSEX buffer.

SysexContainer & get_sysex ()

'Getter' function for member m_sysex from stazed, non-const version for use by midibus.

const SysexContainer & get_sysex () const

'Getter' function for member m_sysex from stazed

void set_sysex_size (int len)

'Setter' function for member m_sysex and m_sysex_size from stazed

int get_sysex_size () const

'Getter' function for member m sysex size

void link (event *ev)

Sets m_has_link and sets m_link to the provided event pointer.

event * get_linked () const

'Getter' function for member m linked

bool is_linked () const

'Getter' function for member m_has_link

· void clear link ()

'Setter' function for member m_has_link

• void paint ()

'Setter' function for member m painted

void unpaint ()

'Setter' function for member m_painted

• bool is painted () const

'Getter' function for member m_painted

void mark ()

'Setter' function for member m marked

• void unmark ()

'Setter' function for member m_marked

• bool is_marked () const

'Getter' function for member m_marked

• void select ()

'Setter' function for member m_selected

· void unselect ()

'Setter' function for member m_selected

• bool is_selected () const

'Getter' function for member m_selected

• void make_clock ()

Sets m_status to EVENT_MIDI_CLOCK;.

midibyte data (int index) const

'Getter' function for member m_data[]

midibyte get_note () const

Assuming m_data[] holds a note, get the note number, which is in the first data byte, m_data[0].

void set_note (midibyte note)

Sets the note number, clearing off the most-significant-bit and assigning it to the first data byte, m_data[0].

void transpose_note (int tn)

Transpose the note, if possible.

midibyte get_note_velocity () const

'Getter' function for member m_data[1], the note velocity.

• void set_note_velocity (int vel)

Sets the note velocity, which is held in the second data byte, and clearing off the most-significant-bit, storing it in m_{data} [1].

bool is_note_on () const

Check for the Note On value in m_status.

• bool is_note_off () const

Check for the Note Off value in m_status.

• bool is_note () const

Returns true if m_status is a Note On, Note Off, or Aftertouch message.

· bool is note off recorded () const

Some keyboards send Note On with velocity 0 for Note Off, so we provide this function to test that during recording.

· void print () const

Prints out the timestamp, data size, the current status byte, any SYSEX data if present, or the two data bytes for the status byte.

int get_rank () const

This function is used in sorting MIDI status events (e.g.

Static Public Member Functions

• static bool is channel msg (midibyte m)

Static test for the channel message/statuse values: Note On, Note Off, Aftertouch, Control Change, Program Change, Channel Pressure, and Pitch Wheel.

static bool is_one_byte_msg (midibyte m)

Static test for channel messages that have only one data byte: Program Change and Channel Pressure.

static bool is two byte msg (midibyte m)

Static test for channel messages that have two data bytes: Note On, Note Off, Control Change, Aftertouch, and Pitch Wheel.

static bool is_note_msg (midibyte m)

Static test for messages that involve notes and velocity: Note On, Note Off, and Aftertouch.

• static bool is strict note msg (midibyte m)

Static test for messages that involve notes only: Note On and Note Off.

static bool is_desired_cc_or_not_cc (midibyte m, midibyte cc, midibyte datum)

Static test for channel messages that are either not control-change messages, or are and match the given controller value.

Private Attributes

· midipulse m timestamp

Provides the MIDI timestamp in ticks, otherwise known as the "pulses" in "pulses per quarter note" (PPQN).

midibyte m_status

This is the status byte without the channel.

· midibyte m channel

In order to be able to handle MIDI channel-splitting of an SMF 0 file, we need to store the channel, even if we override it when playing the MIDI data.

midibyte m data [SEQ64 MIDI DATA BYTE COUNT]

The two bytes of data for the MIDI event.

• SysexContainer m_sysex

The data buffer for SYSEX messages.

• int m_sysex_size

Gives the size of the SYSEX message.

event * m_linked

This event is used to link Note Ons and Offs together.

bool m_has_link

Indicates that a link has been made.

· bool m selected

Answers the question "is this event selected in editing.".

bool m marked

Answers the question "is this event marked in processing.".

bool m painted

Answers the question "is this event being painted.".

12.8.1 Detailed Description

A MIDI event consists of 3 bytes:

```
-# Status byte, 1sssnnn, where the sss bits specify the type of
message, and the nnnn bits denote the channel number.
The status byte always starts with 0.
```

- -# The first data byte, 0xxxxxxx, where the data byte always start with 0, and the xxxxxxx values range from 0 to 127.
- -# The second data byte, 0xxxxxxx.

This class may have too many member functions.

12.8.2 Member Typedef Documentation

12.8.2.1 SysexContainer

```
typedef std::vector<midibyte> seq64::event::SysexContainer
```

12.8.3 Constructor & Destructor Documentation

This function is currently geared only toward support of the SMF 0 channel-splitting feature. Many of the members are not set to useful values when the MIDI file is read, so we don't handle them for now.

Note that now events are also copied when creating the editable_events container, so this function is even more important. The event links, for linking Note Off events to their respective Note On events, are dropped. Generally, they will need to be reconstituted by calling the event list::verify and link() function.

Warning

This function does not yet copy the SysEx data. The inclusion of SysEx events was not complete in Seq24, and it is still not complete in Sequencer64. Nor does it currently bother with the links, as noted above.

rhs Provides the event object to be copied.

```
12.8.3.3 ~event() seq64::event::~event ( ) [virtual]
```

The restart_sysex() function does what we need. But now that m_sysex is a vector, no action is needed.

12.8.4 Member Function Documentation

12.8.4.1 operator=()

This function is currently geared only toward support of the SMF 0 channel-splitting feature. Many of the member are not set to useful value when the MIDI file is read, so we don't handle them for now.

Warning

This function now copies the SysEx data, but the inclusion of SysEx events was not complete in Seq24, and it is still not complete in Sequencer64. Nor does it currently bother with the link the event might have.

Parameters

rhs Provides the event object to be assigned.

Returns

Returns a reference to "this" object, to support the serial assignment of events.

12.8.4.2 operator<()

Otherwise, it returns true if the current timestamp is less than the event's timestamp.

Warning

The less-than operator is supposed to support a "strict weak ordering", and is supposed to leave equivalent values in the same order they were before the sort. However, every time we load and save our sample MIDI file, events get reversed. Here are program-changes that get reversed:

```
Save N: 0070: 6E 00 C4 48 00 C4 0C 00 C4 57 00 C4 19 00 C4 26 Save N+1: 0070: 6E 00 C4 26 00 C4 19 00 C4 57 00 C4 0C 00 C4 48
```

```
The 0070 is the offset within the versions of the b4uacuse-seq24.midi file.
```

Because of this mis-feature, and the very slow speed of loading a MIDI file when Sequencer64 is built for debugging, we are exploring using an std::mulitmap instead of an std::list. Search for occurrences of the SEQ64_USE_EVENT_MAP macro. (This actually works better than a list, for loading MIDI event, we have found, but may cause the upper limit of the number of playing sequences to drop a little, due to the overhead of incrementing multimap iterators versus list iterators).

Parameters

```
rhs The object to be compared against.
```

Returns

Returns true if the time-stamp and "rank" are less than those of the comparison object.

12.8.4.3 set_timestamp()

Parameters

time Provides the time value, in ticks, to set as the timestamp.

12.8.4.4 get_timestamp()

```
midipulse seq64::event::get_timestamp ( ) const [inline]
```

12.8.4.5 get_channel()

```
midibyte seq64::event::get_channel ( ) const [inline]
```

12.8.4.6 check_channel()

```
bool seq64::event::check_channel (
    int channel ) const [inline]
```

Used in the SMF 0 track-splitting code.

Parameters

channel	The channel to check.

Returns

Returns true if the given channel matches the event's channel.

12.8.4.7 is_channel_msg()

This function requires that the channel data have already been masked off.

Parameters

m The channel status or message byte to be tested, with the channel bits masked off.

We could add an optional boolean to cause the channel nybble to be explicitly cleared.

Returns

Returns true if the byte represents a MIDI channel message.

12.8.4.8 is_one_byte_msg()

The rest of the channel messages have two data bytes. This function requires that the channel data have already been masked off.

Parameters

m The channel status or message byte to be tested, with the channel bits masked off.

We could add an optional boolean to cause the channel nybble to be explicitly cleared.

Returns

Returns true if the byte represents a MIDI channel message that has only one data byte. However, if this function returns false, it might not be a channel message at all, so be careful.

12.8.4.9 is_two_byte_msg()

This function requires that the channel data have already been masked off.

m The channel status or message byte to be tested, with the channel bits masked off.

We could add an optional boolean to cause the channel nybble to be explicitly cleared.

Returns

Returns true if the byte represents a MIDI channel message that has two data bytes. However, if this function returns false, it might not be a channel message at all, so be careful.

12.8.4.10 is_note_msg()

This function requires that the channel nybble has already been masked off.

Parameters

m The channel status or message byte to be tested, with the channel bits masked off.

We could add an optional boolean to cause the channel nybble to be explicitly cleared.

Returns

Returns true if the byte represents a MIDI note message.

12.8.4.11 is_strict_note_msg()

Parameters

m The channel status or message byte to be tested, with the channel bits masked off.

Returns

Returns true if the byte represents a MIDI note on/off message.

12.8.4.12 is_desired_cc_or_not_cc()

Note

The old logic was the first line, but can be simplified to the second line; the third line shows the abstract representation. Also made sure of this using a couple truth tables.

```
(m != EVENT_CONTROL_CHANGE) || (m == EVENT_CONTROL_CHANGE && d == cc)
    (m != EVENT_CONTROL_CHANGE) || (d == cc)
    a || (! a && b) => a || b

\param m
    The channel status or message byte to be tested, with the channel bits masked off.

\param cc
    The desired cc value, which the datum must match, if the message is a control-change message.

\param datum
    The current datum, to be compared to cc, if the message is a control-change message.

\return
    Returns true if the message is not a control-change, or if it is and the cc and datum parameters match.
```

12.8.4.13 mod_timestamp()

Parameters

modtick The tick value to mod the timestamp against.

Returns

Returns a value ranging from 0 to _mod-1.

If a_status is a channel event, then the channel portion of the status is cleared using a bitwise AND against $EVE \leftarrow NT_CLEAR_CHAN_MASK$.

Found in yet another fork of seq24:

```
// ORL fait de la merde
```

He also provided a very similar routine: set_status_midibus().

Stazed:

The record parameter, if true, does not clear channel portion on record for channel specific recording. The channel portion is cleared in sequence::stream_event() by calling set_status() (a_record = false) after the matching channel is determined. Otherwise, we use a bitwise AND to clear the channel portion of the status. All events will be stored without the channel nybble. This is necessary since the channel is appended by midibus::play() based on the track.

Instead of adding a "record" parameter to set_status(), we provide a more specific function, set_status_keep_channel(), for use in the mastermidibus class.

Parameters

status

The status byte, perhaps read from a MIDI file or edited in the sequencer's event editor. Sometime, this byte will have the channel nybble masked off. If that is the case, the eventcode/channel overload of this function is more appropriate.

12.8.4.15 set_status() [2/2]

Parameters

eventcode	The status byte, perhaps read from a MIDI file. This byte is assumed to have already had its low nybble cleared by masking against EVENT_CLEAR_CHAN_MASK.
channel	The channel byte. Combined with the event-code, this makes a valid MIDI "status" byte. This byte is assume to have already had its high nybble cleared by masking against EVENT_GET_CHAN_MASK.

12.8.4.16 set_status_keep_channel()

It replaces stazed's set_status() with the optional "record" parameter.

Parameters

code The status byte, generally read from the MIDI buss.	eventcode
--	-----------

12.8.4.17 set_channel()

It actually just sets the m_channel member. Note that the sequence channel generally overrides this value in the usage of the event.

channel	The channel byte to be set.
---------	-----------------------------

12.8.4.18 get_status()

The second byte of data is zeroed. The data bytes are in a two =-byte array member, m_data.

Parameters

d1 The byte value to set as the first data byte.

```
12.8.4.20 set_data() [2/2]
```

Parameters

	The first byte value to set.
d2	The second byte value to set.

12.8.4.21 get_data()

Parameters

	d0	[out] The return reference for the first byte.
ſ	d1	[out] The return reference for the first byte.

12.8.4.22 increment_data1()

```
void seq64::event::increment_data1 ( ) [inline]
```

12.8.4.23 decrement_data1()

We now use a vector instead of an array, so there is no need for reallocation and copying of the current SYSEX data. The data represented by data and dsize is appended to that data buffer.

Parameters

data	Provides the additional SYSEX data. If not provided, nothing is done, and false is returned.
dsize	Provides the size of the additional SYSEX data. If not provided, nothing is done.

Returns

Returns false if there was an EVENT_MIDI_SYSEX_END byte in the appended data, or if an error occurred, and the caller needs to stop trying to process the data. We're not quite sure what to do with any extra data remains.

```
12.8.4.27 append_sysex() [2/2]
```

Parameters

data A single MIDI byte of data, assumed to be part of a SYSEX message event.

12.8.4.28 restart_sysex()

```
void seq64::event::restart_sysex ( )
```

(The m_sysex member used to be a pointer.)

ev

Provides a pointer to the event value to set. If null, then m_has_link is set to false, to guarantee that is_linked() is correct.

```
12.8.4.34 get_linked()
event* seq64::event::get_linked ( ) const [inline]

12.8.4.35 is_linked()
bool seq64::event::is_linked ( ) const [inline]

12.8.4.36 clear_link()

void seq64::event::clear_link ( ) [inline]

12.8.4.37 paint()

void seq64::event::paint ( ) [inline]
```

```
12.8.4.38 unpaint()
void seq64::event::unpaint ( ) [inline]
12.8.4.39 is_painted()
bool seq64::event::is_painted ( ) const [inline]
12.8.4.40 mark()
void seq64::event::mark ( ) [inline]
12.8.4.41 unmark()
void seq64::event::unmark ( ) [inline]
12.8.4.42 is_marked()
bool seq64::event::is_marked ( ) const [inline]
12.8.4.43 select()
void seq64::event::select ( ) [inline]
12.8.4.44 unselect()
void seq64::event::unselect ( ) [inline]
12.8.4.45 is_selected()
bool seq64::event::is_selected ( ) const [inline]
12.8.4.46 make_clock()
void seq64::event::make_clock ( ) [inline]
12.8.4.47 data()
midibyte seq64::event::data (
             int index ) const [inline]
12.8.4.48 get_note()
midibyte seq64::event::get_note ( ) const [inline]
12.8.4.49 set_note()
void seq64::event::set_note (
             midibyte note ) [inline]
```

note Provides the note value to set.

12.8.4.50 transpose_note()

Parameters

tn

The amount (positive or negative) to transpose a note. If the result is out of range, the transposition is not performed.

12.8.4.51 get_note_velocity()

```
midibyte seq64::event::get_note_velocity ( ) const [inline]
```

12.8.4.52 set_note_velocity()

Parameters

vel Provides the velocity value to set.

12.8.4.53 is_note_on()

```
bool seq64::event::is_note_on ( ) const [inline]
```

Currently assumes that the channel nybble has already been stripped.

Returns

Returns true if m_status is EVENT_NOTE_ON.

12.8.4.54 is_note_off()

```
bool seq64::event::is_note_off ( ) const [inline]
```

Currently assumes that the channel nybble has already been stripped.

Returns

Returns true if m_status is EVENT_NOTE_OFF.

12.8.4.55 is_note()

```
bool seq64::event::is_note ( ) const [inline]
```

All of these are notes, associated with a MIDI key value. Uses the static function is note_msg().

Returns

The return value of is_note_msg() is returned.

12.8.4.56 is_note_off_recorded()

```
bool seq64::event::is_note_off_recorded ( ) const [inline]
```

The channel nybble is masked off before the test.

Returns

Returns true if the event is a Note On event with velocity of 0.

12.8.4.57 print()

```
void seq64::event::print ( ) const
```

12.8.4.58 get_rank()

```
int seq64::event::get_rank ( ) const
```

The ranking, from high to low, is note off, note on, aftertouch, channel pressure, and pitch wheel, control change, and program changes.

note on/off, aftertouch, control change, etc.) The sort order is not determined by the actual status values.

The lower the ranking the more upfront an item comes in the sort order.

Returns

Returns the rank of the current m_status byte.

12.8.5 Field Documentation

12.8.5.1 m_timestamp

```
midipulse seq64::event::m_timestamp [private]
```

```
12.8.5.2 m_status
```

```
midibyte seq64::event::m_status [private]
```

The channel is included when recording MIDI, but, once a sequence with a matching channel is found, the channel nybble is cleared for storage. The channel will be added back on the MIDI bus upon playback. The high nibble = type of event; The low nibble = channel. Bit 7 is present in all status bytes.

```
12.8.5.3 m_channel
```

```
midibyte seq64::event::m_channel [private]
```

This member adds another 4 bytes to the event object, most likely.

```
12.8.5.4 m_data
```

```
midibyte seq64::event::m_data[SEQ64_MIDI_DATA_BYTE_COUNT] [private]
```

Remember that the most-significant bit of a data byte is always 0. A one-byte message uses only the 0th index.

```
12.8.5.5 m_sysex
```

```
SysexContainer seq64::event::m_sysex [private]
```

Adapted from Stazed's Seq32 project on GitHub.

```
12.8.5.6 m_sysex_size
```

```
int seq64::event::m_sysex_size [private]
```

Perhaps redundant.

```
12.8.5.7 m_linked
```

```
event* seq64::event::m_linked [private]
```

12.8.5.8 m_has_link

```
bool seq64::event::m_has_link [private]
```

This item is used [via the get_link() and link() accessors] in the sequence class.

12.8.5.9 m_selected

```
bool seq64::event::m_selected [private]
```

12.8.5.10 m_marked

```
bool seq64::event::m_marked [private]
```

12.8.5.11 m_painted

```
bool seq64::event::m_painted [private]
```

12.9 seq64::event_list::event_key Class Reference

Provides a key value for an event map.

Public Member Functions

event_key (midipulse tstamp, int rank)

Principal event_key constructor.

• event_key (const event &e)

Event-based constructor.

• bool operator< (const event_key &rhs) const

Provides the minimal operator needed to sort events using an event_key.

Private Attributes

• midipulse m_timestamp

The primary key-value for the key.

• int m_rank

The sub-key-value for the key.

12.9.1 Detailed Description

Its types match the m_timestamp and get_rank() function of this event class.

12.9.2 Constructor & Destructor Documentation

Parameters

tstamp	The time-stamp is the primary part of the key. It is the most important key item.
rank	Rank is an arbitrary number used to prioritize events that have the same time-stamp. See the
	event::get_rank() function for more information.

This constructor makes it even easier to create an event_key. Note that the call to event::get_rank() makes a simple calculation based on the status of the event.

Parameters

rhs Provides the event key to be copied.

12.9.3 Member Function Documentation

12.9.3.1 operator<()

Parameters

rhs Provides the event key to be compared against.

Returns

Returns true if the rank and timestamp of the current object are less than those of rhs.

12.9.4 Field Documentation

12.9.4.1 m_timestamp

```
midipulse seq64::event_list::event_key::m_timestamp [private]

12.9.4.2 m_rank

int seq64::event_list::event_key::m_rank [private]
```

12.10 seq64::event_list Class Reference

The event_list class is a receptable for MIDI events.

Data Structures

class event_key

Provides a key value for an event map.

Public Member Functions

· event_list ()

Principal constructor.

event_list (const event_list &a_rhs)

Copy constructor.

event_list & operator= (const event_list &a_rhs)

Principal assignment operator.

~event_list ()

A rote destructor.

· iterator begin ()

'Getter' function for member m_events.begin(), non-constant version.

• const_iterator begin () const

'Getter' function for member m_events.begin(), constant version.

· iterator end ()

'Getter' function for member m_events.end(), non-constant version.

· const_iterator end () const

'Getter' function for member m_events.end(), constant version.

· int count () const

Returns the number of events stored in m_events.

• bool empty () const

Returns true if there are no events.

bool add (const event &e)

Adds an event to the internal event list in an optionally sorted manner.

· bool is_modified () const

'Getter' function for member m_is_modified

• void unmodify ()

'Setter' function for member m_is_modified This function may be needed by some of the sequence editors.

void remove (iterator ie)

Provides a wrapper for the iterator form of erase(), which is the only one that sequence uses.

• void clear ()

Provides a wrapper for clear().

void merge (event_list &el, bool presort=true)

Provides a merge operation for the event multimap analogous to the merge operation for the event list.

Static Public Member Functions

• static event & dref (iterator ie)

Wrapper for std::list::sort(), or, since multimaps are always sorted, an empty function.

static const event & dref (const_iterator ie)

Dereference const access for list or map.

Private Types

typedef std::multimap< event_key, event > Events

Types to use to swap between list and multimap implementations.

- typedef std::pair< event_key, event > EventsPair
- typedef std::multimap< event_key, event >::iterator iterator
- typedef std::multimap< event_key, event >::const_iterator const_iterator

Private Member Functions

• void link_new ()

Links a new event.

• void clear links ()

Clears all event links and unmarks them all.

• void verify_and_link (midipulse slength)

This function verifies state: all note-ons have an off, and it links note-offs with their note-ons.

bool mark_selected ()

Marks all selected events.

void mark_out_of_range (midipulse slength)

Marks all events that have a time-stamp that is out of range.

• void mark_all ()

Marks all events.

• void unmark_all ()

Unmarks all events.

• bool remove marked ()

Removes marked events.

void unpaint all ()

Unpaints all list-events.

• int count_selected_notes () const

Counts the selected note-on events in the event list.

• bool any_selected_notes () const

Indicates that at least one note is selected.

• int count_selected_events (midibyte status, midibyte cc) const

Counts the selected events, with the given status, in the event list.

• void select all ()

Selects all events, unconditionally.

void unselect_all ()

Deselects all events, unconditionally.

void print () const

Prints a list of the currently-held events.

· const Events & events () const

'Getter' function for member m_events

Private Attributes

Events m_events

This list holds the current pattern/sequence events.

• bool m_is_modified

A new flag to indicate if an event was added or removed.

Friends

- · class editable_events
- · class midi container
- · class midi splitter
- class sequence

12.10.1 Detailed Description

Two implementations, an std::multimap, and the original, an std::list, are provided for comparison, and are selected at build time, by manually defining the SEQ64_USE_EVENT_MAP macro near the top of this module.

12.10.2 Member Typedef Documentation

seq64::event_list::~event_list ()

```
12.10.2.1 Events
typedef std::multimap<event_key, event> seq64::event_list::Events [private]
12.10.2.2 EventsPair
typedef std::pair<event_key, event> seq64::event_list::EventsPair [private]
12.10.2.3 iterator
typedef std::multimap<event_key, event>::iterator seq64::event_list::iterator [private]
12.10.2.4 const_iterator
typedef std::multimap<event_key, event>::const_iterator seq64::event_list::const_iterator
[private]
12.10.3 Constructor & Destructor Documentation
12.10.3.1 event_list() [1/2]
seq64::event_list::event_list ( )
12.10.3.2 event_list() [2/2]
seq64::event_list::event_list (
             const event_list & rhs )
Parameters
      Provides the event list to be copied.
12.10.3.3 ∼event_list()
```

12.10.4 Member Function Documentation

Follows the stock rules for such an operator, just assigning member values.

Parameters

rhs Provides the event list to be assigned.

```
12.10.4.2 begin() [1/2]
iterator seq64::event_list::begin ( ) [inline]
12.10.4.3 begin() [2/2]
const_iterator seq64::event_list::begin ( ) const [inline]
12.10.4.4 end() [1/2]
iterator seq64::event_list::end ( ) [inline]
12.10.4.5 end() [2/2]
const_iterator seq64::event_list::end ( ) const [inline]
12.10.4.6 count()
int seq64::event_list::count ( ) const [inline]
We like returning an integer instead of size t, and rename the function so nobody is fooled.
12.10.4.7 empty()
bool seq64::event_list::empty ( ) const [inline]
```

return m_events.size() == 0;

12.10.4.8 add()

It is a wrapper, wrapper for insert() or push_front(), with an option to call sort().

For the std::multimap implementation, This is an option if we want to make sure the insertion succeed.

If the std::list implementation has been built in, then the event list is sorted after the addition. This is a time-consuming operation.

Warning

This pushing (and, in writing the MIDI file, the popping), causes events with identical timestamps to be written in reverse order. Doesn't affect functionality, but it's puzzling until one understands what is happening. That's why we're now preferring to use a multimap as the container.

Parameters

e Provides the event to be added to the list.

Returns

Returns true if the insertion succeeded, as evidenced by an increment in container size.

12.10.4.9 is_modified()

```
bool seq64::event_list::is_modified ( ) const [inline]
```

12.10.4.10 unmodify()

```
void seq64::event_list::unmodify ( ) [inline]
```

But use it with great caution.

12.10.4.11 remove()

Currently, no check on removal is performed. Set the modified-flag.

Parameters

ie Provides the iterator to the event to be removed.

We have certain constraints to preserve, as the following discussion shows.

For std::list, sequence merges list T into list A by first calling T.sort(), and then A.merge(T). The merge() operation merges T into A by transferring all of its elements, at their respective ordered positions, into A. Both containers must already be ordered.

The merge effectively removes all the elements in T (which becomes empty), and inserts them into their ordered position within container (which expands in size by the number of elements transferred). The operation is performed without constructing nor destroying any element, whether T is an Ivalue or an rvalue, or whether the value-type supports move-construction or not.

Each element of T is inserted at the position that corresponds to its value according to the strict weak ordering defined by operator <. The resulting order of equivalent elements is stable (i.e. equivalent elements preserve the relative order they had before the call, and existing elements precede those equivalent inserted from x). The function does nothing if (&x == this).

For std::multimap, sorting is automatic. However, unless move-construction is supported, merging will be less efficient than for the list version. Also, we need a way to include duplicates of each event, so we need to use a multimap. Once all this setup, merging is really just insertion. And, since sorting isn't needed, the multimap actually turns out to be faster.

Parameters

el	Provides the event list to be merged into the current event list.
presort	If true, the events are presorted. This is a requirement for merging an std::list, but is a no-op for the
	std::multimap implementation.

Dereference access for list or map.

Parameters

ie Provides the iterator to the event to which to get a reference.

ie Provides the iterator to the event to which to get a reference.

12.10.4.16 link_new()

```
void seq64::event_list::link_new ( ) [private]
```

This function checks for a note on, then look for its note off. This function is provided in the event_list because it does not depend on any external data. Also note that any desired thread-safety must be provided by the caller.

12.10.4.17 clear_links()

```
void seq64::event_list::clear_links ( ) [private]
```

12.10.4.18 verify_and_link()

Stazed (seq32):

```
This function now deletes any notes that are \geq= m_length, so any resize or move of notes must modify for wrapping if Note Off is \geq= m_length.
```

Not threadsafe As in most case, the caller will use an automutex to call this function safely.

Parameters

slength Provides the length beyond which events will be pruned.

12.10.4.19 mark_selected()

```
bool seq64::event_list::mark_selected ( ) [private]
```

Returns

Returns true if there was even one event selected and marked.

12.10.4.20 mark_out_of_range()

Used for killing (pruning) those events not in range. If the current time-stamp is greater than the length, then the event is marked for pruning.

Note

This code was comparing the timestamp as greater than or equal to the sequence length. However, being equal is fine. This may explain why the midifile code would add one tick to the length of the last note when processing the end-of-track.

Parameters

	slength	Provides the length beyond which events will be pruned.
--	---------	---

12.10.4.21 mark_all()

```
void seq64::event_list::mark_all ( ) [private]
```

Not yet used, but might come in handy with the event editor dialog.

12.10.4.22 unmark_all()

```
void seq64::event_list::unmark_all ( ) [private]
```

12.10.4.23 remove_marked()

```
bool seq64::event_list::remove_marked ( ) [private]
```

Note how this function handles removing a value to avoid incrementing a now-invalid iterator.

Threadsafe

Returns

Returns true if at least one event was removed.

12.10.4.24 unpaint_all()

```
void seq64::event_list::unpaint_all ( ) [private]
```

12.10.4.25 count_selected_notes()

```
int seq64::event_list::count_selected_notes ( ) const [private]
```

12.10.4.26 any_selected_notes()

```
bool seq64::event_list::any_selected_notes ( ) const [private]
```

Acts like event_list::count_selected_notes(), but stops after finding a selected note. We could add a flag to count
__selected_notes() to break, I suppose.

Returns

Returns true if at least one note is selected.

12.10.4.27 count_selected_events()

If the event is a control change (CC), then it must also match the given CC value.

Parameters

statu	The desired status value to count.	
СС	The desired control-change to count. Used only if the status parameter indicates a control-change event.	1

Returns

Returns the number of selected events.

```
12.10.4.28 select_all()
```

12.10.4.29 unselect_all()

void seq64::event_list::select_all () [private]

```
void seq64::event_list::unselect_all ( ) [private]
```

12.10.4.30 print()

```
void seq64::event_list::print ( ) const [private]
```

12.10.4.31 events()

```
const Events& seq64::event_list::events ( ) const [inline], [private]
```

12.10.5 Friends And Related Function Documentation

```
12.10.5.1 editable_events
friend class editable_events [friend]
12.10.5.2 midi_container
friend class midi_container [friend]
12.10.5.3 midi_splitter
friend class midi_splitter [friend]
12.10.5.4 sequence
friend class sequence [friend]
12.10.6 Field Documentation
12.10.6.1 m_events
Events seq64::event_list::m_events [private]
12.10.6.2 m_is_modified
```


bool seq64::event_list::m_is_modified [private]

We may need to give client code a way to reload the sequence. This is currently an issue when a seqroll and an eventedit/eventslots are active for the same sequence.

12.11 seq64::eventedit Class Reference

This class supports an Event Editor that is used to tweak the details of events and get a better idea of the mix of events in a sequence.

Inheritance diagram for seq64::eventedit:



Public Member Functions

eventedit (perform &p, sequence &seq)

Principal constructor, has a reference to a perform object.

virtual ∼eventedit ()

This rote constructor does nothing.

Private Member Functions

void enqueue_draw ()

Helper wrapper for calling eventslots::queue draw().

void set_seq_title (const std::string &title)

Sets m_label_seq_name to the title.

void set_seq_time_sig (const std::string &sig)

Sets m_label_time_sig to the time-signature string.

void set_seq_ppqn (const std::string &p)

Sets m_label_ppqn to the parts-per-quarter-note string.

void set_seq_count ()

Sets m_label_ev_count to the number-of-events string.

void set_event_category (const std::string &c)

Sets m_label_category to the category string.

void set event timestamp (const std::string &ts)

Sets m_entry_ev_timestamp to the time-stamp string.

void set_event_name (const std::string &n)

Sets m_entry_ev_name to the name-of-event string.

void set_event_data_0 (const std::string &d)

Sets m_entry_ev_data_0 to the first data byte string.

void set_event_data_1 (const std::string &d)

Sets m_entry_data_1 to the second data byte string.

void perf_modify ()

Provides a way to mark the perform object as modified, when the modified sequence is saved.

• void set_dirty (bool flag=true)

Sets the "modified" status of the user-interface.

void v_adjustment (int value)

Sets the parameters for the vertical scroll-bar, using only the value parameter.

void v_adjustment (int value, int lower, int upper)

Sets the parameters for the vertical scroll-bar that is associated with the eventslots event-list user-interface.

void change_focus (bool set_it=true)

Changes what perform and mainwid see as the "current sequence".

· void close_out ()

Handles closing the sequence editor, common code for handle_cancel() and handle_close().

void handle_close ()

Handles closing the sequence editor.

void handle_delete ()

Initiates the deletion of the current editable event.

void handle_insert ()

Initiates the insertion of a new editable event.

void handle_modify ()

Passes the edited fields to the current editable event in the eventslot.

• void handle save ()

Handles saving the edited data back to the original sequence.

void handle_cancel ()

Cancels the edits and closes the dialog box.

· void on_realize ()

This callback function calls the base-class on_realize() function.

void on set focus (Widget *focus)

On receiving focus, attempt to tell mainwid that this sequence is now the current sequence.

bool on_focus_in_event (GdkEventFocus *)

Implements the on-focus event handling.

bool on_focus_out_event (GdkEventFocus *)

Implements the on-unfocus event handling.

bool on_key_press_event (GdkEventKey *ev)

This function is the callback for a key-press event.

bool on delete event (GdkEventAny *event)

Handles an on-delete event.

Private Attributes

Gtk::Table * m_table

A whole horde of GUI elements.

• Gtk::Adjustment * m vadjust

Vertical paging for event list.

• Gtk::VScrollbar * m_vscroll

Vertical scroll for event list.

• eventslots * m_eventslots

Drawing area for events.

• Gtk::HBox * m_htopbox

Padding at the top of the dialog.

• Gtk::VBox * m showbox

Area for sequence information.

Gtk::VBox * m_editbox

Text-edits and buttons for data.

• Gtk::VBox * m optsbox

Reserved for future options.

• Gtk::HBox * m_bottbox

Holds the Save and Close buttons.

• Gtk::VBox * m rightbox

Used for padding on right side.

• Gtk::Button * m_button_del

"Delete Current Event (*)" button.

• Gtk::Button * m_button_ins

"Insert New Event" button.

• Gtk::Button * m button modify

"Modify New Event" button.

Gtk::Button * m_button_save

"Save to Sequence" button.

• Gtk::Button * m button cancel

"Close" button.

• Gtk::Label * m label seg name

Items for the inside of the m_showbox member.

• Gtk::Label * m label time sig

Shows time signature for pattern.

• Gtk::Label * m_label_ppqn

Shows the parts per quarter note.

• Gtk::Label * m_label_channel

Shows channel number of pattern.

• Gtk::Label * m label ev count

Shows the count of pattern events.

Gtk::Label * m_label_spacer

Spacer for the showbox elements.

• Gtk::Label * m_label_modified

Shows "[Modified]" if edited.

• Gtk::Label * m_label_category

Items for the inside of the m editbox member.

• Gtk::Entry * m_entry_ev_timestamp

Text edit for event time-stamp.

• Gtk::Entry * m_entry_ev_name

Text edit for MIDI event name.

• Gtk::Entry * m_entry_ev_data_0

Text edit for first event datum.

• Gtk::Entry * m_entry_ev_data_1

Text edit for second event datum.

• Gtk::Label * m label time fmt

Optsbox item, only "Sequencer64".

• Gtk::Label * m_label_right

Padding at the right of dialog.

• sequence & m_seq

A reference to the sequence being edited, to control its editing flag.

• bool m_have_focus

Indicates that the focus has already been changed to this sequence.

Friends

· class eventslots

Additional Inherited Members

12.11.1 Constructor & Destructor Documentation

12.11.1.1 eventedit()

We've reordered the pointer members and put them in the initializer list to make the constructor a bit cleaner.

Adjustment parameters:

```
value initial value lower minimum value upper maximum value step_increment step increment page_increment page_size page_size
```

Table constructor parameters:

rows columns homogenous

Table attach() parameters:

```
child widget to add.

left_attach column number to attach left side of a child widget right_attach column number to attach right side of a child widget top_attach row number to attach the top of a child widget bottom_attach row number to attach the bottom of a child widget xoptions properties of the child widget when table resized yoptions same as xoptions, except vertical.

xpadding padding on L and R of widget added to table ypadding amount of padding above and below the child widget
```

Layout:

Parameters

р	Refers to the main performance object.	
seq	Refers to the sequence holding the event data to be edited.	

The sequedit class indirectly sets the sequence dirty flags, and this allows the sequence's pattern slot to be updated, which, for example, allows the new experimental in-edit-highlight feature to work. To get the eventedit to also show the in-edit highlighting, we can make the sequence::set_dirty_mp() call. This call does not cause a prompt for saving the file when exiting.

```
12.11.1.2 ~eventedit()
seq64::eventedit::~eventedit ( ) [virtual]
```

We're going to have to run the application through valgrind to make sure that nothing is left behind.

12.11.2 Member Function Documentation

```
12.11.2.1 enqueue_draw()

void seq64::eventedit::enqueue_draw ( ) [private]

12.11.2.2 set_seq_title()

void seq64::eventedit::set_seq_title ( const std::string & title ) [private]

Parameters

title The name of the sequence.

12.11.2.3 set_seq_time_sig()

void seq64::eventedit::set_seq_time_sig ( const std::string & sig ) [private]

Parameters

sig The time signature of the sequence.
```

12.11.2.4 set_seq_ppqn()

Parameters

p The parts-per-quarter-note string for the sequence.

12.11.2.5 set_seq_count()

```
void seq64::eventedit::set_seq_count ( ) [private]
```

12.11.2.6 set_event_category()

Parameters

c The category string for the current event.

12.11.2.7 set_event_timestamp()

Parameters

ts The time-stamp string for the current event.

12.11.2.8 set_event_name()

Parameters

n The name-of-event string for the current event.

12.11.2.9 set_event_data_0()

Parameters

d The first data byte string for the current event.

12.11.2.10 set_event_data_1()

```
void seq64::eventedit::set_event_data_1 (
    const std::string & d ) [private]
```

Parameters

d The second data byte string for the current event.

12.11.2.11 perf_modify()

```
void seq64::eventedit::perf_modify ( ) [private]
```

12.11.2.12 set_dirty()

```
void seq64::eventedit::set_dirty (
          bool flag = true ) [private]
```

This includes changing a label and enabling/disabling the Save button.

Parameters

flag If true, the modified status is indicated, otherwise it is cleared.

This function overload provides a common use case.

Parameters

value The new current value to be indicated by the scroll-bar.

12.11.2.14 v_adjustment() [2/2]

It keeps the frame scroll-bar in sync with the frame movement actions. Some of the parameters are obtained from the eventslots object:

```
Page size comes from eventslots::line_maximum().Page increment is a little less than the page-size value.
```

Parameters

value	The current value to be indicated by the scroll-bar. It will lie between the lower and upper parameter.	
lower	The lowest value to be indicated by the scroll-bar.	
upper	The highest value to be indicated by the scroll-bar.	

12.11.2.15 change_focus()

Similar to the same function in sequedit.

Parameters

set⊷	If true (the default value), indicates we want focus, otherwise we want to give up focus.
_it	

```
12.11.2.16 close_out()

void seq64::eventedit::close_out ( ) [private]

12.11.2.17 handle_close()

void seq64::eventedit::handle_close ( ) [private]

Simply calls close_out().

12.11.2.18 handle_delete()

void seq64::eventedit::handle_delete ( ) [private]

12.11.2.19 handle_insert()

void seq64::eventedit::handle_insert ( ) [private]
```

The event's location will be determined by the timestamp and existing events. Note that we have to recalibrate the scroll-bar when we insert/delete events by calling v_adjustment().

```
12.11.2.20 handle_modify()
void seq64::eventedit::handle_modify ( ) [private]
```

Note that there are two cases to worry about. If the timestamp has not changed, then we can simply modify the existing current event in place. Otherwise, we need to delete the old event and insert the new one. But that is done for us by eventslots::modify_current_event().

```
12.11.2.21 handle_save()
void seq64::eventedit::handle_save ( ) [private]
```

The event list in the original sequence is cleared, and the editable events are converted to plain events, and added to the container, one by one.

Todo Could also support writing the events to a new sequence, for added flexibility.

12.11.2.22 handle_cancel()

```
void seq64::eventedit::handle_cancel ( ) [private]
```

In order for removing the current-highlighting in the mainwd or perfedit windows, some of the work of handle_close() needs to be done here as well.

12.11.2.23 on_realize()

```
void seq64::eventedit::on_realize ( ) [private]
```

Then it sets the vertical adjustment to account for the number of events in the eventslot.

12.11.2.24 on_set_focus()

Only works in certain circumstances.

Parameters

focus The widget that has the focus. Merely passed on to gui_window_gtk2's version of this function.

12.11.2.25 on_focus_in_event()

It sets the focus flag and calls change_focus().

12.11.2.26 on_focus_out_event()

It resets the focus flag and calls change_focus().

12.11.2.27 on_key_press_event()

If the Up or Down arrow is pressed (later, k and j :-), then we tell the eventslots object to move the "current event" highlighting up or down. In Gtkmm, these arrows also cause movement from one edit field to the next, so we disable that process if the event was handled here.

Note that the Delete key is needed for the edit fields. For now, we replace it with the asterisk, which is easy to access from the numeric pad of a keyboard, and allows for rapid deletion. The Insert key also causes confusing effects in the edit fields, so we replaced it by the slash, but that didn't work. Note that the asterisk and slash should not be required in any of the edit fields. HOWEVER, "/" still gets passed the edit fields (!), so you'll just have to click the button to insert an event. Let's try the backslash! No go there, either.

Parameters

```
ev The key event to process.
```

Returns

Returns true if the event got handled somewhere along the line.

12.11.2.28 on_delete_event()

It sets the sequence object's editing flag to false, and deletes "this". This function is called if the "Close" ("X") button in the window's title bar is clicked. That is a different action from clicking the Close button.

Returns

Always returns false.

12.11.3 Friends And Related Function Documentation

12.11.3.1 eventslots

```
friend class eventslots [friend]
```

12.11.4 Field Documentation

```
12.11.4.1 m_table
```

```
Gtk::Table* seq64::eventedit::m_table [private]
```

Provides the layout table for UI.

12.11.4.2 m_vadjust

```
Gtk::Adjustment* seq64::eventedit::m_vadjust [private]
```

12.11.4.3 m_vscroll

Gtk::VScrollbar* seq64::eventedit::m_vscroll [private]

12.11.4.4 m_eventslots

eventslots* seq64::eventedit::m_eventslots [private]

```
12.11.4.5 m_htopbox
Gtk::HBox* seq64::eventedit::m_htopbox [private]
12.11.4.6 m_showbox
Gtk::VBox* seq64::eventedit::m_showbox [private]
12.11.4.7 m_editbox
Gtk::VBox* seq64::eventedit::m_editbox [private]
12.11.4.8 m_optsbox
Gtk::VBox* seq64::eventedit::m_optsbox [private]
12.11.4.9 m_bottbox
Gtk::HBox* seq64::eventedit::m_bottbox [private]
12.11.4.10 m_rightbox
Gtk::VBox* seq64::eventedit::m_rightbox [private]
12.11.4.11 m_button_del
Gtk::Button* seq64::eventedit::m_button_del [private]
12.11.4.12 m_button_ins
Gtk::Button* seq64::eventedit::m_button_ins [private]
12.11.4.13 m_button_modify
Gtk::Button* seq64::eventedit::m_button_modify [private]
12.11.4.14 m_button_save
Gtk::Button* seq64::eventedit::m_button_save [private]
```

Shows the type of MIDI event.

```
12.11.4.15 m_button_cancel
Gtk::Button* seq64::eventedit::m_button_cancel [private]
12.11.4.16 m_label_seq_name
Gtk::Label* seq64::eventedit::m_label_seq_name [private]
Shows the name of the pattern.
12.11.4.17 m_label_time_sig
Gtk::Label* seq64::eventedit::m_label_time_sig [private]
12.11.4.18 m_label_ppqn
Gtk::Label* seq64::eventedit::m_label_ppqn [private]
12.11.4.19 m_label_channel
Gtk::Label* seq64::eventedit::m_label_channel [private]
12.11.4.20 m_label_ev_count
Gtk::Label* seq64::eventedit::m_label_ev_count [private]
12.11.4.21 m_label_spacer
Gtk::Label* seq64::eventedit::m_label_spacer [private]
12.11.4.22 m_label_modified
Gtk::Label* seq64::eventedit::m_label_modified [private]
12.11.4.23 m_label_category
Gtk::Label* seq64::eventedit::m_label_category [private]
```

```
12.11.4.24 m_entry_ev_timestamp
Gtk::Entry* seq64::eventedit::m_entry_ev_timestamp [private]
12.11.4.25 m_entry_ev_name
Gtk::Entry* seq64::eventedit::m_entry_ev_name [private]
12.11.4.26 m_entry_ev_data_0
Gtk::Entry* seq64::eventedit::m_entry_ev_data_0 [private]
12.11.4.27 m_entry_ev_data_1
Gtk::Entry* seq64::eventedit::m_entry_ev_data_1 [private]
12.11.4.28 m_label_time_fmt
Gtk::Label* seq64::eventedit::m_label_time_fmt [private]
12.11.4.29 m_label_right
Gtk::Label* seq64::eventedit::m_label_right [private]
12.11.4.30 m_seq
sequence& seq64::eventedit::m_seq [private]
12.11.4.31 m_have_focus
bool seq64::eventedit::m_have_focus [private]
```

This item is to modify the mainwid and perfedit "edit-sequence" value in order to highlight pattern slot of the pattern/event editor that currently has the user-input focus.

12.12 seq64::eventslots Class Reference

This class implements the left-side list of events in the pattern event-edit window.

Inheritance diagram for seq64::eventslots:



Public Member Functions

• eventslots (perform &p, eventedit &parent, sequence &seq, Gtk::Adjustment &vadjust)

Principal constructor for this user-interface object.

virtual ∼eventslots ()

Let's provide a do-nothing virtual destructor.

• int event count () const

'Getter' function for member m_event_count Returns the number of total events in the sequence represented by the eventslots object.

• int line_count () const

'Getter' function for member m_line_count Returns the current number of rows (events) in the eventslots's display.

int line maximum () const

'Getter' function for member m_line_maximum Returns the maximum number of rows (events) in the eventslots's display.

int line_increment () const

Provides the "page increment" or "line increment" of the frame, This value is the current line-maximum of the frame minus its overlap value.

• int top_index () const

'Getter' function for member m_top_index

• int current_index () const

'Getter' function for member m_current_index

int pager_index () const

'Getter' function for member m_pager_index

Private Member Functions

· bool load events ()

Grabs the event list from the sequence and uses it to fill the editable-event list.

• void set_current_event (const editable_events::iterator ei, int index, bool full_redraw=true)

Set the current event, which is the event that is highlighted.

bool insert_event (const editable_event &edev)

Inserts an event.

• bool insert_event (const std::string &evtimestamp, const std::string &evname, const std::string &evdata0, const std::string &evdata1)

Inserts an event based on the setting provided, which the eventedit object gets from its Entry fields.

• bool delete_current_event ()

Deletes the current event, and makes adjustments due to that deletion.

bool modify_current_event (const std::string &evtimestamp, const std::string &evname, const std::string &evdata0, const std::string &evdata1)

Modifies the data in the currently-selected event.

• bool save events ()

Writes the events back to the sequence.

void select_event (int event_index=SEQ64_NULL_EVENT_INDEX, bool full_redraw=true)

Selects and highlights the event that is located in the frame at the given event index.

 void set_text (const std::string &evcategory, const std::string &evtimestamp, const std::string &evname, const std::string &evdata0, const std::string &evdata1)

Sets the text in the parent dialog, eventedit.

• void enqueue draw ()

Wraps queue_draw().

int convert_y (int y)

Converts a y-value into an event index relative to 0 (the top of the eventslots window/pixmap) and returns it.

void draw event (editable events::iterator ei, int index)

Draw the given slot/event.

void draw_events ()

Draws all of the events in the current eventslots frame.

· void change_vert ()

Change the vertical offset of events.

void page_movement (int new_value)

Adjusts the vertical position of the frame according to the given new scrollbar/vadjust value.

void page_topper (editable_events::iterator newcurrent)

Adjusts the vertical position of the frame according to the given new bottom iterator.

• int decrement top ()

Decrements the top iterator, if possible.

• int increment_top ()

Increments the top iterator, if possible.

int decrement_current ()

Decrements the current iterator, if possible.

int increment_current ()

Increments the current iterator, if possible.

• int decrement bottom ()

Decrements the bottom iterator, if possible.

• int increment_bottom ()

Increments the bottom iterator, if possible.

· void on_realize ()

Handles the callback when the window is realized.

bool on_expose_event (GdkEventExpose *ev)

Handles an on-expose event.

• bool on_button_press_event (GdkEventButton *ev)

Provides the callback for a button press, and it handles only a left mouse button.

• bool on_button_release_event (GdkEventButton *ev)

Currently does nothing.

• bool on_focus_in_event (GdkEventFocus *ev)

This callback is an attempt to get keyboard focus into the eventslots pixmap area.

bool on_focus_out_event (GdkEventFocus *ev)

This callback handles an out-of-focus event by resetting the flag HAS_FOCUS.

• bool on_scroll_event (GdkEventScroll *ev)

Handle the scrolling of the window.

void on_size_allocate (Gtk::Allocation &)

Handles a size-allocation event.

void on_move_up ()

Move to the previous event.

void on_move_down ()

Move to the next event.

void on_frame_up ()

Move to the previous frame.

• void on_frame_down ()

Move to the next frame.

• void on_frame_home ()

Move to the first frame.

• void on_frame_end ()

Move to the last frame.

Private Attributes

· eventedit & m_parent

Provides a link to the eventedit that created this object.

sequence & m_seq

Provides a reference to the sequence that this dialog is meant to view or modify.

• editable_events m_event_container

Holds the editable events for this sequence.

· int m slots chars

Provides the number of the characters in the name box.

• int m_char_w

Provides the "real" width of a character.

• int m_setbox_w

Provides the width of the "set number" box.

int m_slots_x

Provides the width of the names box, which is the width of a character for 24 characters.

· int m_slots_y

Provides the height of the names box, which is hardwired to 24 pixels.

· int m event count

The current number of events in the edited container.

int m_line_count

Counts the number of displayed events, which depends on how many events there are (m_event_count) and the size of the event list (m_line_maximum).

· int m line maximum

Counts the maximum number of displayed events, which depends on the size of the event list (and thus the size of the dialog box for the event editor).

· int m line overlap

Provides a little overlap for paging through the frame.

int m_top_index

The index of the event that is 0th in the visible list of events.

• int m_current_index

Indicates the index of the current event within the frame.

editable_events::iterator m_top_iterator

Provides the top "pointer" to the start of the editable-events section that is being shown in the user-interface.

· editable_events::iterator m_bottom_iterator

Provides the bottom "pointer" to the end of the editable-events section that is being shown in the user-interface.

• editable events::iterator m current iterator

Provides the "pointer" to the event currently in focus.

• int m_pager_index

Indicates the event index that matches the index value of the vertical pager.

Friends

· class eventedit

Additional Inherited Members

12.12.1 Constructor & Destructor Documentation

```
12.12.1.1 eventslots()
seq64::eventslots::eventslots (
             perform & p,
             eventedit & parent,
             sequence & seq,
             Gtk::Adjustment & vadjust )
12.12.1.2 ∼eventslots()
virtual seq64::eventslots::\simeventslots ( ) [inline], [virtual]
12.12.2 Member Function Documentation
12.12.2.1 event_count()
int seq64::eventslots::event_count ( ) const [inline]
12.12.2.2 line_count()
int seg64::eventslots::line_count ( ) const [inline]
12.12.2.3 line_maximum()
int seq64::eventslots::line_maximum ( ) const [inline]
12.12.2.4 line_increment()
int seq64::eventslots::line_increment ( ) const [inline]
12.12.2.5 top_index()
int seq64::eventslots::top_index ( ) const [inline]
12.12.2.6 current_index()
int seq64::eventslots::current_index ( ) const [inline]
```

12.12.2.7 pager_index()

```
int seq64::eventslots::pager_index ( ) const [inline]
```

12.12.2.8 load_events()

```
bool seq64::eventslots::load_events ( ) [private]
```

Determines how many events can be shown in the GUI [later] and adjusts the top and bottom editable-event iterators to show the first page of events.

Returns

Returns true if the event iterators were able to be set up as valid.

12.12.2.9 set_current_event()

Note in the snprintf() calls that the first digit is part of the data byte, so that translation is easier.

Parameters

ei	The iterator that points to the event.	
index	The index (re 0) of the event, starting at the top line of the frame. It is a frame index, not a container index.	
full_redraw	If true (the default) does a full redraw of the frame. Otherwise, only the current event is drawn. Generally, the only time a single event (actually, two adjacent events) is convenient to draw is when using the arrow keys, where the speed of keystroke auto-repeats makes the full-frame update scrolling very flickery and disconcerting.	

12.12.2.10 insert_event() [1/2]

What actually happens here depends if the new event is before the frame, within the frame, or after the frame, based on the timestamp.

If before the frame: To keep the previous events visible, we do not need to increment the iterators (insertion does not affect multimap iterators), but we do need to increment their indices. The contents shown in the frame should not change.

If at the frame top: The new timestamp equals the top timestamp. We don't know exactly where the new event goes in the multimap, but we do have an new event.

If at the frame bottom: TODO

If after the frame: No action needed if the bottom event is actually at the bottom of the frame. But if the frame is not yet filled, we need to increment the bottom iterator, and its index.

Note

Actually, it is far easier to just adjust all the counts and iterators and redraw the screen, as done by the page_topper() function.

Parameters

```
edev The event to insert, prebuilt.
```

Returns

Returns true if the event was inserted.

12.12.2.11 insert_event() [2/2]

It calls the other insert_event() overload.

Note that we need to qualify the temporary event class object we create below, with the seq64 namespace, otherwise the compiler thinks we're trying to access some Gtkmm thing.

Parameters

evtimestamp	The time-stamp of the new event, as obtained from the event-edit timestamp field.	
evname	The type name (status name) of the new event, as obtained from the event-edit event-name	
	field.	
evdata0	The first data byte of the new event, as obtained from the event-edit data 1 field.	
evdata1	The second data byte of the new event, as obtained from the event-edit data 2 field. Used only	
	for two-parameter events.	

Returns

Returns true if the event was inserted.

12.12.2.12 delete_current_event()

```
bool seq64::eventslots::delete_current_event ( ) [private]
```

To delete the current event, this function moves the current iterator to the next event, deletes the previously-current iterator, adjusts the event count and the bottom iterator, and redraws the pixmap. The exact changes depend upon whether the deleted event was at the top of the visible frame, within the visible frame, or at the bottom the visible frame. Note that only visible events can be the current event, and thus get deleted.

Basically, when an event is deleted, the frame (delimited by the event-index members) stays in place, while the frame iterators move to the previous event. If the top of the frame would move to before the first event, then the frame must shrink.

Top case: If the current iterator is the top (of the frame) iterator, then the top iterator needs to be incremented. The new top event has the same index as the now-gone top event. The index of the bottom event is decremented, since an event before it is now gone. The bottom iterator moves to the next event, which is now at the bottom of the frame. The current event is treated like the top event.

Inside case: If the current iterator is in the middle of the frame, the top iterator and index remain unchanged. The current iterator is incremented, but its index is now the same as the old bottom index. Same for the bottom iterator.

Bottom case: If the current iterator (and bottom iterator) point to the last event in the frame, then both of them need to be decremented. The frame needs to be moved up by one event, so that the current event remains at the bottom (it's just simpler to manage that way).

If there is no event after the bottom of the frame, the iterators that now point to end() must backtrack one event. If the container becomes empty, then everything is invalidated.

Returns

Returns true if the delete was possible. If the container was empty or became empty, then false is returned.

12.12.2.13 modify_current_event()

If the timestamp has changed, however, we can't just modify the event in place. Instead, we finish modifying the event, but tell the caller to delete and reinsert the new event (in its proper new location based on timestamp).

This function always copies the original event, modifiles the copy, deletes the original event, and inserts the "new" event into the editable-event container.

Parameters

evtimestamp	Provides the new event time-stamp as edited by the user.
evname	Provides the event name as edited by the user.
evdata0	Provides the first data byte as edited by the user.
Ge ppedepth by Doxyge	Provides the second data byte as edited by the user.

Returns

Returns true simply if the event-count is greater than 0.

12.12.2.14 save_events()

```
bool seq64::eventslots::save_events ( ) [private]
```

Also sets the dirty flag for the sequence, via the sequence::add_event() function, but this doesn't seem to set the perform dirty flag. So now we pass the modification buck to the parent, who passes it to the perform object.

We added a copy_events() function in the sequence class to replace add_event() for the purpose of reconstructing the events container for the sequence. It is locked by a mutex, and so will not draw until all is done, preventing a nasty segfault (all segfaults are nasty).

We create a new plain event container here, and then passing it to the new locked/threadsafe sequence::copy_
events() function that clears the sequence container and copies the events from the parameter container.

Note that this code will operate event if all events were deleted.

Returns

Returns true if the operations succeeded.

12.12.2.15 select_event()

```
void seq64::eventslots::select_event (
    int event_index = SEQ64_NULL_EVENT_INDEX,
    bool full_redraw = true ) [private]
```

The event index is provided by converting the y-coordinate of the mouse pointer into a slot number, and then an event index (actually the slot-distance from the m top iterator. Confusing, yes no?

Note that, if the event index is negative, then we just queue up a draw operation, which should paint an empty frame – the event container is empty.

Parameters

event_index	Provides the numeric index of the event in the event frame, or SEQ64_NULL_EVENT if there is	
	no event to draw.	
full_redraw	Defaulting to true, this parameter can be set to false in some case to reduce the flickering of the	
	frame under fast movement.	

12.12.2.16 set_text()

const std::string & evdata0,
const std::string & evdata1) [private]

Parameters

evcategory	The category of event to be set in the parent.
evtimestamp	The event time-stamp to be set in the parent.
evname	The event name to be set in the parent.
evdata0	The first event data byte to be set in the parent.
evdata1	The second event data byte to be set in the parent.

12.12.2.17 enqueue_draw()

```
void seq64::eventslots::enqueue_draw ( ) [private]
```

12.12.2.18 convert_y()

Parameters

y The y coordinate of the position of the mouse click in the eventslot window/pixmap.

Returns

Returns the index of the event position in the user-interface, which should range from 0 to m_line_count.

12.12.2.19 draw_event()

The slot contains the event details in (so far) one line of text in the box:

```
| timestamp | event kind | channel | data 0 name + value | data 1 name + value
```

Currently, this view shows only events that get copied to the sequence's event list. This rules out the following items from the view:

```
- MThd (song header)
- MTrk and Meta TrkEnd (track marker, a sequence has only one track)
- SeqNr (sequence number)
- SeqSpec (but there are three that might appear, see below)
- Meta TrkName
```

The events that are shown in this view are:

```
- One-data-value events:
- Program Change
- Channel Pressure
- Two-data-value events:
- Note Off
- Note On
- Aftertouch
- Control Change
- Pitch Wheel
- Other:
- SysEx events, with partial show of data bytes
- SeqSpec events (TBD):
- Key
- Scale
- Background sequence
```

The index of the event is shown in the editor portion of the eventedit dialog.

```
12.12.2.20 draw_events()
void seq64::eventslots::draw_events ( ) [private]
```

It first clears the whole bitmap to white, so that no artifacts from the previous state of the frame are left behind.

Need to figure out how to calculate the number of displayable events.

```
m_line_maximum = ???

12.12.2.21 change_vert()

void seq64::eventslots::change_vert ( ) [private]
```

Note that m_vadjust is the Gtk::Adjustment object that the eventedit parent passes to the gui_drawingarea_gtk2 constructor.

The top-event and bottom-event indices (and their corresponding editable-event iterators) delimit the part of the event container that is displayed in the eventslots user-interface. The top-event index starts at 0, and the bottom-event is larger (initially, by 42 slots).

When the scroll-bar thumb moves up or down, we need to change both event indices and both event iterators by the corresponding amount. Luckily, the std::multimap iterator is bidirectional.

Note that we may need to reduce the movement of events to a value less than a page; it can be limited backwards by the value of the top index, and forward by the value of the bottom index.

The adjustment is done via movement from the current position.

Do we even need a way to detect excess movement? The scrollbar, if properly set up, should never move the frame too high or too low. Verified by testing.

Parameters

new_value	Provides the new value of the scrollbar position.
-----------	---

12.12.2.23 page_topper()

The adjustment is done "from scratch". We've found page movement to be an insoluable problem in some editing circumstances. So now we move to the inserted event, and make it the top event.

However, always moving an inserted event to the top is a bit annoying. So now we backtrack so that the inserted event is at the bottom.

Parameters

newcurrent	Provides the iterator to the event to be shown at the bottom of the frame.
------------	--

12.12.2.24 decrement_top()

```
int seq64::eventslots::decrement_top ( ) [private]
```

Returns

Returns 0, or SEQ64_NULL_EVENT_INDEX if the iterator could not be decremented.

12.12.2.25 increment_top()

```
int seq64::eventslots::increment_top ( ) [private]
```

Also handles the top-event index, so that the GUI can display the proper event numbers.

Returns

Returns the top index, or SEQ64_NULL_EVENT_INDEX if the iterator could not be incremented, or would increment to the end of the container.

12.12.2.26 decrement_current()

```
int seq64::eventslots::decrement_current ( ) [private]
```

Returns

Returns the decremented index, or SEQ64_NULL_EVENT_INDEX if the iterator could not be decremented. Remember that the index ranges only from 0 to m_line_count-1, and that is enforced here.

12.12.2.27 increment_current()

```
int seq64::eventslots::increment_current ( ) [private]
```

Returns

Returns the incremented index, or SEQ64_NULL_EVENT_INDEX if the iterator could not be incremented. Remember that the index ranges only from 0 to m line count-1, and that is enforced here.

12.12.2.28 decrement_bottom()

```
int seq64::eventslots::decrement_bottom ( ) [private]
```

Returns

Returns 0, or SEQ64_NULL_EVENT_INDEX if the iterator could not be decremented.

12.12.2.29 increment_bottom()

```
int seq64::eventslots::increment_bottom ( ) [private]
```

There is an issue in paging down using the scrollbar where, at the bottom of the scrolling, the bottom iterator ends up bad. Not yet sure how this happens, so for now we backtrack one event if this happens.

Returns

Returns the incremented index, or SEQ64_NULL_EVENT_INDEX if the iterator could not be incremented.

12.12.2.30 on_realize()

```
void seq64::eventslots::on_realize ( ) [private]
```

It first calls the base-class version of on_realize(). Then it allocates any additional resources needed.

12.12.2.31 on_expose_event()

It draws all of the sequences.

12.12.2.32 on_button_press_event()

```
12.12.2.33 on_button_release_event()
```

See the same function in the perfroll module.

```
12.12.2.35 on_focus_out_event()
```

```
bool seq64::eventslots::on_focus_out_event (
    GdkEventFocus * ev ) [private]
```

12.12.2.36 on_scroll_event()

12.12.2.37 on_size_allocate()

It first calls the base-class version of this function.

```
12.12.2.38 on_move_up()
```

```
void seq64::eventslots::on_move_up ( ) [private]
```

We must scroll up if the event is now before the frame, and should be made the new top event of the frame. Note that this function isn't really an event-response callback. It is called by eventedit::on_key_press_event().

```
12.12.2.39 on_move_down()
```

```
void seq64::eventslots::on_move_down ( ) [private]
```

We must scroll down if the event is now after the frame. Note that this function isn't really an event-response callback. It is called byh eventedit::on_key_press_event().

12.12.2.40 on_frame_up()

```
void seq64::eventslots::on_frame_up ( ) [private]
```

```
12.12.2.41 on_frame_down()
void seq64::eventslots::on_frame_down ( ) [private]
12.12.2.42 on_frame_home()
void seq64::eventslots::on_frame_home ( ) [private]
12.12.2.43 on_frame_end()
void seq64::eventslots::on_frame_end ( ) [private]
12.12.3 Friends And Related Function Documentation
12.12.3.1 eventedit
friend class eventedit [friend]
12.12.4 Field Documentation
12.12.4.1 m_parent
eventedit& seq64::eventslots::m_parent [private]
12.12.4.2 m_seq
sequence& seq64::eventslots::m_seq [private]
12.12.4.3 m_event_container
editable_events seq64::eventslots::m_event_container [private]
12.12.4.4 m_slots_chars
int seq64::eventslots::m_slots_chars [private]
Pretty much hardwired to 64 at present. It helps determine the m_slots_x value (the width of the eventslots list).
12.12.4.5 m_char_w
int seq64::eventslots::m_char_w [private]
```

Generated by Doxygen

This value is obtained from a font-renderer accessor function.

12.12.4.6 m_setbox_w

```
int seq64::eventslots::m_setbox_w [private]
```

This used to be hardwired to 6 * 2 (character-width times two).

```
12.12.4.7 m_slots_x
int seq64::eventslots::m_slots_x [private]
12.12.4.8 m_slots_y
```

int seq64::eventslots::m_slots_y [private]

This value was once 22 pixels, but we need a little extra room for our new font. This extra room is compatible enough with the old font, as well.

```
12.12.4.9 m_event_count
```

```
int seq64::eventslots::m_event_count [private]
```

12.12.4.10 m_line_count

```
int seq64::eventslots::m_line_count [private]
```

12.12.4.11 m_line_maximum

```
int seq64::eventslots::m_line_maximum [private]
```

12.12.4.12 m_line_overlap

```
int seq64::eventslots::m_line_overlap [private]
```

12.12.4.13 m_top_index

```
int seq64::eventslots::m_top_index [private]
```

It is used in numbering the events that are shown in the event-slot frame. Do not confuse it with m_current_index, which is relative to the frame, not the container-beginning.

12.12.4.14 m_current_index

```
int seq64::eventslots::m_current_index [private]
```

This event will also be pointed to by the m_current_event iterator. Do not confuse it with m_top_index, which is relative to the container-beginning, not the frame.

```
12.12.4.15 m_top_iterator
editable_events::iterator seq64::eventslots::m_top_iterator [private]

12.12.4.16 m_bottom_iterator
editable_events::iterator seq64::eventslots::m_bottom_iterator [private]

12.12.4.17 m_current_iterator
editable_events::iterator seq64::eventslots::m_current_iterator [private]

12.12.4.18 m_pager_index
int seq64::eventslots::m_pager_index [private]
```

12.13 seq64::font Class Reference

This class provides a wrapper for rendering fonts that are encoded as a 16 x 16 pixmap file in XPM format.

Public Types

enum Color {
 BLACK,
 WHITE,
 BLACK_ON_YELLOW,
 YELLOW_ON_BLACK,
 BLACK_ON_CYAN,
 CYAN_ON_BLACK }

A simple enumeration to describe the basic colors used in writing text.

Public Member Functions

• font ()

Rote default constructor, except that it does add 1 to the cf_text_h or co_text_h values to use in m_padded_h.

void init (Glib::RefPtr< Gdk::Window > windo)

Initialization function for a window on which fonts will be drawn.

void render_string_on_drawable (Glib::RefPtr< Gdk::GC > m_gc, int x, int y, Glib::RefPtr< Gdk::Drawable > drawable, const char *str, font::Color col, bool invert=false) const

Draws a text string.

· int char width () const

'Getter' function for member m_font_w

• int char_height () const

'Getter' function for member m font h

• int padded_height () const

'Getter' function for member m_padded_h

Private Attributes

· bool m_use_new_font

If true, use the new font, which is a little bit more modern looking, and is also thicker, and thus a little easier to see.

int m_cell_w

Specifies the cell width of the whole character cell.

• int m_cell_h

Specfies the cell height of the whole character cell.

· int m font w

Specifies the exact width of a character cell, in pixels.

• int m_font_h

Specifies the exact height of a character cell, in pixels.

• int m_offset

Provides an ad hoc small horizontal or vertical offset for printing strings.

int m padded h

Provides a common constant used by much of the drawing code, but only marginally related to the padded character height.

const Glib::RefPtr< Gdk::Pixmap > * m_pixmap

Points to the current pixmap (m_black_pixmap or m_white_pixmap) to use to render a string.

Glib::RefPtr< Gdk::Pixmap > m_black_pixmap

The pixmap in the file src/pixmaps/font_b.xpm is loaded into this object.

Glib::RefPtr< Gdk::Pixmap > m white pixmap

The pixmap in the file src/pixmaps/font_w.xpm is loaded into this object.

Glib::RefPtr< Gdk::Pixmap > m_b_on_y_pixmap

The pixmap in the file src/pixmaps/font_y.xpm is loaded into this object.

Glib::RefPtr< Gdk::Pixmap > m_y_on_b_pixmap

The pixmap in the file $src/pixmaps/font_yb.xpm$ is loaded into this object.

• Glib::RefPtr< Gdk::Pixmap> m_b_on_c_pixmap

The pixmap in the file src/pixmaps/cyan_wenfont_y.xpm is loaded into this object.

Glib::RefPtr< Gdk::Pixmap > m_c_on_b_pixmap

The pixmap in the file src/pixmaps/cyan_wenfont_yb.xpm is loaded into this object.

• Glib::RefPtr< Gdk::Bitmap > m_clip_mask

This object is instantiated as a default object.

12.13.1 Member Enumeration Documentation

12.13.1.1 Color

```
enum seq64::font::Color
```

Basically, these two values cause the selection of one or another pixmap (font_b_xpm and font_w_xpm). We've added two more pixmaps to draw black text on a yellow background (font_y.xpm) and yellow text on a black background (font_yb.xpm). Oh, and couple more for cyan and black text-blitting.

Enumerator

BLACK	The first supported color. A black font on a white background.
WHITE	The second supported color. A white font on a black background.
BLACK_ON_YELLOW	A new color, for drawing black text on a yellow background.
YELLOW_ON_BLACK	A new color, for drawing yellow text on a black background.
BLACK_ON_CYAN	A new color, for drawing black text on a cyan background.
CYAN_ON_BLACK	A new color, for drawing cyan text on a black background.

Generated by Doxygen

12.13.2 Constructor & Destructor Documentation

```
12.13.2.1 font()
seq64::font::font ( )
```

12.13.3 Member Function Documentation

This function loads four pixmaps that contain the characters to be used to draw text strings.

One pixmap has white characters on a black background, one has black characters on a white background, one has yellow characters on a black background, and one has black characters on a yellow background.

Parameters

wp Provides the windows pointer for the window that holds the color map.

12.13.3.2 render_string_on_drawable()

This function grabs the proper font bitmap, extracts the current character pixmap from it, and slaps it down where it needs to be to render the character in the string.

Parameters

gc	Provides the graphics context for drawing the text using GTK+.	
Х	The horizontal location of the text.	
У	The vertical location of the text.	
a_draw	The drawable object on which to draw the text.	
str	The string to draw. Should use a constant string reference instead.	
col	The font color to use to draw the string. The supported values are font::BLACK, font::WHITE, font::BLACK_ON_YELLOW, font::YELLOW_ON_BLACK. The actual correct colors are provided by selecting one of four font pixmaps, as described in the init() function.	
invert	t If true, apply color inversion, if specified.	

```
12.13.3.3 char_width()
int seq64::font::char_width ( ) const [inline]
12.13.3.4 char_height()
int seq64::font::char_height ( ) const [inline]
12.13.3.5 padded_height()
int seq64::font::padded_height ( ) const [inline]
12.13.4 Field Documentation
12.13.4.1 m use new font
bool seq64::font::m_use_new_font [private]
12.13.4.2 m_cell_w
int seq64::font::m_cell_w [private]
12.13.4.3 m_cell_h
int seq64::font::m_cell_h [private]
12.13.4.4 m_font_w
int seq64::font::m_font_w [private]
```

Currently defaults to cf_text_w = 6. Note that a lot of stuff depends on this being 6 at present, even with our new, slightly wider, font.

```
12.13.4.5 m_font_h
int seq64::font::m_font_h [private]
```

Currently defaults to cf text h = 10. Note that a lot of stuff depends on this being 10 at present, even with our new, slightly wider, font. But some of the drawing code doesn't use the character height, but the padded character height.

12.13.4.6 m_offset

int seq64::font::m_offset [private]

12.13.4.7 m_padded_h

```
int seq64::font::m_padded_h [private]
```

12.13.4.8 m_pixmap

```
const Glib::RefPtr<Gdk::Pixmap>* seq64::font::m_pixmap [mutable], [private]
```

This member used to be an object, but it's probably a bit faster to just use a pointer (or a reference).

12.13.4.9 m_black_pixmap

```
Glib::RefPtr<Gdk::Pixmap> seq64::font::m_black_pixmap [private]
```

It contains a black font on a white background. The new-style font, if selected, is in the resources/pixmaps/wenfont ← _b.xmp pixmap.

12.13.4.10 m white pixmap

```
Glib::RefPtr<Gdk::Pixmap> seq64::font::m_white_pixmap [private]
```

It contains a black font on a white background. The new-style font, if selected, is in the resources/pixmaps/wenfont — _w.xmp pixmap.

12.13.4.11 m_b_on_y_pixmap

```
Glib::RefPtr<Gdk::Pixmap> seq64::font::m_b_on_y_pixmap [private]
```

It contains a black font on a yellow background. The new-style font, if selected, is in the resources/pixmaps/wenfont-_y.xmp pixmap.

12.13.4.12 m_y_on_b_pixmap

```
Glib::RefPtr<Gdk::Pixmap> seq64::font::m_y_on_b_pixmap [private]
```

It contains a yellow font on a black background. The new-style font, if selected, is resources/pixmaps/wenfont ← _yb.xmp pixmap.

12.13.4.13 m_b_on_c_pixmap

```
Glib::RefPtr<Gdk::Pixmap> seq64::font::m_b_on_c_pixmap [private]
```

It contains a black font on a cyan background. It is available only for the new font-style.

12.13.4.14 m_c_on_b_pixmap

```
Glib::RefPtr<Gdk::Pixmap> seq64::font::m_c_on_b_pixmap [private]
```

It contains a cyan font on a black background. It is available only for the new font-style.

12.13.4.15 m_clip_mask

```
Glib::RefPtr<Gdk::Bitmap> seq64::font::m_clip_mask [private]
```

All we know is it seems to be a requirement for creating a pixmap object from an XMP file.

12.14 seq64::FruityPerfInput Class Reference

Implements the performance input of that certain fruity sequencer that people seem to like.

Inheritance diagram for seq64::FruityPerfInput:

seq64::AbstractPerfInput - m adding - m adding pressed + AbstractPerfInput() #~AbstractPerfInput() # on_button_press_event() # on_button_release_event() # on_motion_notify_event() # activate adding() # handle_motion_key() # is adding() # set adding() # is adding pressed() # set_adding_pressed() seq64::FruityPerfInput - m_current_x - m_current_y + FruityPerfInput() + on button press event() + on button release event() + on_motion_notify_event() - update_mouse_pointer() - on_left_button_pressed() - on_right_button_pressed() - activate adding() handle motion key()

Public Member Functions

• FruityPerfInput ()

Default constructor.

• bool on_button_press_event (GdkEventButton *ev, perfroll &roll)

Handles a button-press event in the Fruity manner.

bool on_button_release_event (GdkEventButton *ev, perfroll &roll)

Handles a button-release event.

• bool on_motion_notify_event (GdkEventMotion *ev, perfroll &roll)

Handles a Fruity motion-notify event.

Private Member Functions

void update_mouse_pointer (perfroll &roll)

Updates the mouse pointer, implementing a context-sensitive mouse.

• bool on_left_button_pressed (GdkEventButton *ev, perfroll &roll)

Handles the left button of the mouse.

• bool on_right_button_pressed (GdkEventButton *ev, perfroll &roll)

Handles the right button of the mouse.

- virtual void activate_adding (bool, perfroll &)
- virtual bool handle_motion_key (bool, perfroll &)

Private Attributes

• long m_current_x

The current x value of the mouse.

long m_current_y

The current y value of the mouse.

Friends

· class perfroll

Additional Inherited Members

12.14.1 Constructor & Destructor Documentation

```
12.14.1.1 FruityPerfInput()
```

```
seq64::FruityPerfInput::FruityPerfInput ( ) [inline]
```

12.14.2 Member Function Documentation

12.14.2.1 on_button_press_event()

ev	The button-press event to process.
roll	The song editor piano roll that is the "parent" of this class.

Returns

Returns true if a modification occurred.

Implements seq64::AbstractPerfInput.

```
12.14.2.2 on_button_release_event()
```

Why is m_adding_pressed modified conditionally when the same modification is then made unconditionally?

Parameters

ev	The button-release event to process.
roll	The song editor piano roll that is the "parent" of this class.

Returns

Returns true if a modification occurred.

Implements seq64::AbstractPerfInput.

```
12.14.2.3 on_motion_notify_event()
```

Parameters

ev	The motion-notify event to process.
roll	The song editor piano roll that is the "parent" of this class.

Returns

Returns true if a modification occurred, and sets the perform modified flag based on that result.

Implements seq64::AbstractPerfInput.

12.14.2.4 update_mouse_pointer()

Note that perform::convert_xy() returns its values via side-effects on the last two parameters.

Parameters

```
roll The song editor piano roll that is the "parent" of this class.
```

12.14.2.5 on_left_button_pressed()

It can handle splitting triggers (?), adding notes, and the following clicks to resize the event, or move it, depending on where clicked:

```
    clicked left side: begin a grow/shrink for the left side
    clicked right side: grow/shrink the right side
    clicked in the middle - move it
```

I don't get it, though... all three buttons are handled in the generic button-press callback. Oh, this is just a helper function.

Parameters

ev	The left-button-press event to process.
roll	The song editor piano roll that is the "parent" of this class.

Returns

Now returns true if a modification occurred.

12.14.2.6 on_right_button_pressed()

I don't get it, though... all three buttons are handled in the generic button-press callback. Oh, this is a helper function.

ev	The right-button-press event to process.
roll	The song editor piano roll that is the "parent" of this class.

Returns

Returns true if a modification occurred.

```
12.14.2.7 activate_adding()
```

Implements seq64::AbstractPerfInput.

12.14.2.8 handle_motion_key()

Implements seq64::AbstractPerfInput.

12.14.3 Friends And Related Function Documentation

12.14.3.1 perfroll

```
friend class perfroll [friend]
```

12.14.4 Field Documentation

```
12.14.4.1 m_current_x
```

```
long seq64::FruityPerfInput::m_current_x [private]
```

12.14.4.2 m_current_y

```
long seq64::FruityPerfInput::m_current_y [private]
```

12.15 seq64::FruitySeqEventInput Struct Reference

This structure implements the interaction methods for the "fruity" mode of operation.

Public Member Functions

FruitySeqEventInput ()

Default constructor.

void update_mouse_pointer (seqevent &ths)

Provides support for a context-sensitive mouse.

• bool on_button_press_event (GdkEventButton *ev, seqevent &ths)

Implements the on-button-press event callback.

• bool on_button_release_event (GdkEventButton *ev, seqevent &ths)

Implements the on-button-release callback.

bool on_motion_notify_event (GdkEventMotion *ev, seqevent &ths)

Implements the on-motion-notify callback.

Data Fields

• bool m_justselected_one

Indicates that the left mouse button was click to start a selection.

• bool m_is_drag_pasting_start

Set to true when the mouse button is pressed and we're starting to drag some notes to move them and paste them to a different location.

• bool m_is_drag_pasting

Set to true when the left mouse button is pressed for dragging and pasting, set to false when the mouse button is released to drop the pasted items.

12.15.1 Constructor & Destructor Documentation

12.15.1.1 FruitySeqEventInput()

```
\verb|seq64::FruitySeqEventInput::FruitySeqEventInput () | [inline]|\\
```

12.15.2 Member Function Documentation

12.15.2.1 update_mouse_pointer()

Parameters

seqev

Provides the sequent pane (actually a strip on the sequent window) to update to show the proper mouse cursor (left pointer, center pointer, and pencil).

12.15.2.2 on button press event()

Handles dragging and other actions.

The first thing is to set the values for dragging, then reset the box that holds the dirty redraw spot. If pasting, undo the clipboard, and paste the selected events.

Otherwise, process the mouse actions. The current steps shown below are my initial guesses, to be verified at some point.

1. Left button:

- (a) Click:
 - i. A click and release without a drag, or without a Ctrl-Shift, deselects the events.
 - ii. A direct click on an event selects only that event.
- (b) Click-drag:
 - i. If events already selected, adds note and length to the selected notes.
 - ii. Otherwise, select the notes and events.
 - iii. If no events selected in the end, undo the selection.
- · Ctrl-left button:
 - TODO.

The opening part of this function matches that of Seq24SeqEventInput :: on_button_press_event().

Parameters

ev	The button event for the press of a mouse button.
seqev	Provides the sequeent strip to be affected by this button event.

Returns

Returns true if a modification was made. It used to return true all the time.

12.15.2.3 on_button_release_event()

Parameters

ev	The button event for the press of a mouse button.
seqev	Provides the seqevent strip to be affected by this button event.

Returns

Returns true if a modification was made. It used to return true all the time.

12.15.2.4 on_motion_notify_event()

Parameters

ev	The button event for the press of a mouse button.
seqev	Provides the sequeent strip to be affected by this button event.

Returns

Returns true if a modification occurred, and sets the perform modified flag based on that result.

12.15.3 Field Documentation

12.15.3.1 m_justselected_one

```
bool seq64::FruitySeqEventInput::m_justselected_one
```

12.15.3.2 m_is_drag_pasting_start

```
\verb|bool seq64::FruitySeqEventInput::m_is\_drag\_pasting\_start|\\
```

12.15.3.3 m_is_drag_pasting

bool seq64::FruitySeqEventInput::m_is_drag_pasting

12.16 seq64::FruitySeqRollInput Class Reference

Implements the fruity mouse interaction paradigm for the seqroll.

Public Member Functions

FruitySeqRollInput ()

Default constructor.

void update_mouse_pointer (seqroll &ths)

Updates the mouse pointer, implementing a context-sensitive mouse.

• bool on_button_press_event (GdkEventButton *ev, seqroll &ths)

Implements the fruity on-button-press callback.

bool on_button_release_event (GdkEventButton *ev, seqroll &ths)

Implements the fruity handling for the on-button-release event.

• bool on_motion_notify_event (GdkEventMotion *ev, seqroll &ths)

Implements the fruity handling for the on-motion-notify event.

Private Attributes

• bool m_erase_painting

Set to tru if we hold the right mouse button down (in "fruity" mode) and start to drag the mouse around, erasing notes.

• int m_drag_paste_start_pos [2]

Holds the original position of the mouse when ctrl-left-click-drag is done, and is used to make sure that the action doesn't occur until a movement of at least 6 pixels has occurred, to avoid unintended actions caused by minimal jitter in the user's hands.

12.16.1 Constructor & Destructor Documentation

12.16.1.1 FruitySeqRollInput()

```
seq64::FruitySeqRollInput::FruitySeqRollInput ( ) [inline]
```

12.16.2 Member Function Documentation

12.16.2.1 update_mouse_pointer()

Parameters

```
sroll Provides the "parent" of this interaction class.
```

12.16.2.2 on_button_press_event()

This function now uses the needs_update flag to determine if the perform object should modify().

Parameters

ev	The button event.
sroll	The parent of this "fruity" interaction class.

Returns

Returns the value of needs update. It used to return only true.

12.16.2.3 on_button_release_event()

ev	The button event.
sroll	The parent of this "fruity" interaction class.

Returns

Returns the value of needs_update. It used to return only true.

If in moving mode, adjust for snap and convert deltas into screen coordinates. Since delta_note was from delta_y, it will be flipped (delta_y[0] = note[127], etc.), so we have to adjust.

12.16.2.4 on_motion_notify_event()

Parameters

ev	ev The motion event.	
srol	The parent of this "fruity" interaction class. (Why not just inherit and save all these indirect accesses to the segroll? Well, that would make it more difficult to change the mode of interation, in the Options	
	menu, on the fly.)	

Returns

Returns the value of needs_update.

In "fruity" interaction mode, ctrl-left-click-drag on selected note(s) starts a copy/unselect/paste. Doesn't begin the paste until the mouse moves a few pixels, to filter out the unsteady hand.

12.16.3 Field Documentation

12.16.3.1 m_erase_painting

```
bool seq64::FruitySeqRollInput::m_erase_painting [private]
```


12.16.3.2 m_drag_paste_start_pos

```
int seq64::FruitySeqRollInput::m_drag_paste_start_pos[2] [private]
```

12.17 seq64::gui_assistant Class Reference

This class provides an interface for some of the GUI support needed in Sequencer64.

Inheritance diagram for seq64::gui_assistant:



Public Member Functions

gui_assistant (keys_perform &kp)

This constructor wires in some externally (for now) created objects.

virtual ~gui_assistant ()

Stock base-class implementation of a virtual destructor.

- virtual void quit ()=0
- virtual void jack_idle_connect (jack_assistant &jack)=0
- virtual void lash_timeout_connect (lash *lashobject)=0
- const keys_perform & keys () const

 ${\it 'Getter' function for member m_keys_perform The const getter.}$

keys_perform & keys ()

'Getter' function for member m_keys_perform The un-const getter.

Private Attributes

keys_perform & m_keys_perform

Provides a reference to the app-specific GUI-specific keys_perform-derived object that an application is going to use for handling sequence-control keys.

12.17.1 Detailed Description

It also contain a number of helper objects that all kind of go together; only this assistant object will need to be passed around (by non-GUI code).

12.17.2 Constructor & Destructor Documentation

Parameters

p Provides a set of key codes to be used by the perform object to control patterns and their performance.

```
12.17.2.2 ~gui_assistant()
virtual seq64::gui_assistant::~gui_assistant ( ) [inline], [virtual]
12.17.3 Member Function Documentation
12.17.3.1 quit()
virtual void seq64::gui_assistant::quit ( ) [pure virtual]
Implemented in seq64::gui_assistant_gtk2.
12.17.3.2 jack_idle_connect()
virtual void seq64::gui_assistant::jack_idle_connect (
              jack_assistant & jack ) [pure virtual]
Implemented in seq64::gui_assistant_gtk2.
12.17.3.3 lash_timeout_connect()
virtual void seq64::gui_assistant::lash_timeout_connect (
              lash * lashobject ) [pure virtual]
Implemented in seq64::gui_assistant_gtk2.
12.17.3.4 keys() [1/2]
```

const keys_perform& seq64::gui_assistant::keys () const [inline]

```
12.17.3.5 keys() [2/2]
keys_perform& seq64::gui_assistant::keys ( ) [inline]


12.17.4 Field Documentation

12.17.4.1 m_keys_perform
keys_perform& seq64::gui_assistant::m_keys_perform [private]
```

12.18 seq64::gui_assistant_gtk2 Class Reference

This class provides an interface for some of the Gtk/Gdk/Glib support needed in Sequencer64.

Inheritance diagram for seq64::gui_assistant_gtk2:



Public Member Functions

• gui_assistant_gtk2 ()

This class provides an interface for some of the Gtk/Gdk/Glib support needed in Sequencer64.

virtual ~gui assistant gtk2 ()

Virtual classes require a virtual destructor.

virtual void quit ()

Calls the Glib Main object's quit() function.

virtual void lash_timeout_connect (lash *lashobject)

Connects the LASH timeout-event callback to the Glib timeout object.

virtual void jack_idle_connect (jack_assistant &jack)

Connects the JACK session-event callback to the Glib idle object.

Static Private Attributes

12.18.1.1 gui_assistant_gtk2()

static keys_perform_gtk2 sm_internal_keys
 Provides a pre-made keys_perform object.

12.18.1 Constructor & Destructor Documentation

```
seq64::gui_assistant_gtk2::gui_assistant_gtk2 ( )

12.18.1.2 ~gui_assistant_gtk2()
```

virtual seq64::gui_assistant_gtk2::~gui_assistant_gtk2 () [inline], [virtual]

12.18.2 Member Function Documentation

The time-out value is set to 250 ms.

Implements seq64::gui_assistant.

12.18.2.3 jack_idle_connect()

If JACK session support is not enabled, we might emit a message. This mainly prevents a compiler warning about an unused parameter.

Implements seq64::gui_assistant.

12.18.3 Field Documentation

12.18.3.1 sm_internal_keys


```
keys_perform_gtk2 seq64::gui_assistant_gtk2::sm_internal_keys [static], [private]
```

This object is set into the reference provided in the gui_assistant base class.

12.19 seq64::gui_drawingarea_gtk2 Class Reference

Implements the basic drawing areas of the application.

Inheritance diagram for seq64::gui_drawingarea_gtk2:



Data Structures

struct rect

A small helper structure representing a rectangle.

Public Member Functions

gui_drawingarea_gtk2 (perform &p, int window_x=0, int window_y=0)

Perform-only constructor.

• gui_drawingarea_gtk2 (perform &a_perf, Gtk::Adjustment &a_hadjust, Gtk::Adjustment &a_vadjust, int window x=0, int window y=0)

Principal constructor.

virtual ~gui_drawingarea_gtk2 ()

Provides a destructor to delete allocated objects.

• int window x () const

'Getter' function for member m_window_x

• int window_y () const

'Getter' function for member m window y

int current_x () const

'Getter' function for member m_current_x

int current_y () const

'Getter' function for member m_current_y

int drop_x () const

'Getter' function for member m_drop_x

• int drop_y () const

'Getter' function for member m_drop_y

Protected Member Functions

virtual void force_draw ()

Provides a common function for redrawing.

• perform & perf ()

'Getter' function for member m_mainperf

void clear_window ()

Clears the main window.

• void set_line (Gdk::LineStyle ls, int width=1)

A small wrapper function for readability in line-drawing.

void draw_line (int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on the window.

void draw_line (const Color &c, int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on the window after setting the given foreground color.

void draw_line_on_pixmap (int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on the pixmap.

void draw_line_on_pixmap (const Color &c, int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on the pixmap after setting the given foreground color.

void draw_line (Glib::RefPtr< Gdk::Pixmap > &pixmap, int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on any pixmap (not a drawable, though, due to a compiler error after setting the given foreground color.

void draw_line (Glib::RefPtr< Gdk::Pixmap > &pixmap, const Color &c, int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on the pixmap after setting the given foreground color.

• void draw line (Glib::RefPtr< Gdk::Drawable > &drawable, int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on any pixmap (not a drawable, though, due to a compiler error after setting the given foreground color.

void draw line (Glib::RefPtr< Gdk::Drawable > &drawable, const Color &c, int x1, int y1, int x2, int y2)

A small wrapper function to draw a line on the drawable after setting the given foreground color.

void render_string (int x, int y, const std::string &s, font::Color color, bool invert=false)

A small wrapper function for readability in string-drawing to the window.

void render_string_on_pixmap (int x, int y, const std::string &s, font::Color color, bool invert=false)

A small wrapper function for readability in string-drawing to the pixmap.

void draw_rectangle (int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on the window.

• void draw_rectangle (const Color &c, int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing.

void draw rectangle (Glib::RefPtr < Gdk::Drawable > &drawable, int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on a "drawable" context, where the foreground color has already been specified.

• void draw_rectangle (Glib::RefPtr< Gdk::Drawable > &drawable, const Color &c, int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on any drawable context.

• void draw rectangle (Glib::RefPtr< Gdk::Pixmap > &pixmap, int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on a "pixmap" context, where the foreground color has already been specified.

• void draw_rectangle (Glib::RefPtr< Gdk::Pixmap > &pixmap, const Color &c, int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on any pixmap context.

void draw_rectangle_on_pixmap (int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on the pixmap.

void draw_rectangle_on_pixmap (const Color &c, int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on the pixmap.

• void draw_normal_rectangle_on_pixmap (int x, int y, int lx, int ly, bool fill=true)

A small wrapper function for readability in box-drawing on the pixmap.

· void draw_drawable (int xsrc, int ysrc, int xdest, int ydest, int width, int height)

Provides the most common use case for redrawing.

· void scroll_hadjust (Gtk::Adjustment &hadjust, double step)

This function provides optimization for the on_scroll_event() functions, and should provide support for having the segedit/segroll/segtime/segdata panes follow the scrollbar, in a future upgrade (now partly in place).

void scroll_vadjust (Gtk::Adjustment &vadjust, double step)

This function is the vertical version of the scroll_hadjust() function, intended for adding keystroke vertical scrolling using the Page-Up and Page-Down keys, as a new feature of Sequencer64.

- void scroll_hset (Gtk::Adjustment &hadjust, double value)
- void scroll vset (Gtk::Adjustment &vadjust, double value)
- void set current drop x (int x)

Sets the current x value and the drop x value.

void set_current_drop_y (int y)

Sets the current y value and the drop y value.

void on_realize ()

For this GTK callback, on realization of window, initialize the shiz.

Protected Attributes

Glib::RefPtr< Gdk::GC > m gc

The graphics context, which is required for ever drawing and rendering operation.

Glib::RefPtr< Gdk::Window > m_window

Provides the default "window".

• Gtk::Adjustment & m vadjust

Provides an object for vertical "adjustments".

Gtk::Adjustment & m_hadjust

Provides an object for horizontal "adjustments".

Glib::RefPtr< Gdk::Pixmap > m_pixmap

Provides the default "pixmap".

Glib::RefPtr< Gdk::Pixmap > m background

Another pixmap, used for backgrounds.

Glib::RefPtr< Gdk::Pixmap > m_foreground

Another pixmap, used for foregrounds.

• perform & m_mainperf

A frequent hook into the main perform object.

• int m_window_x

Window sizes.

· int m_window_y

Window height value.

int m current x

The x and y value of the current location of the mouse (during dragging?)

int m_current_y

Current mouse y value.

• int m_drop_x

These values are used when roping and highlighting a bunch of events.

• int m_drop_y

Current mouse y-drop value.

Private Member Functions

- gui_drawingarea_gtk2 (const gui_drawingarea_gtk2 &)
- gui_drawingarea_gtk2 & operator= (const gui_drawingarea_gtk2 &)
- void gtk drawarea init ()

Does basic initialization for each of the constructors.

Additional Inherited Members

12.19.1 Detailed Description

Note that this class really "isn't" a gui_pallete_gtk2; it should simply "have" one. But that base class must be derived from Gtk::DrawingArea. We don't want to waste some space by using a "has-a" relationship, and also put up with having to access the palette indirectly. So, in this case, we tolerate the less strict implementation.

12.19.2 Constructor & Destructor Documentation

```
12.19.2.2 gui_drawingarea_gtk2() [2/3]
seq64::gui\_drawingarea\_gtk2::gui\_drawingarea\_gtk2 (
             perform & p,
             int window_x = 0,
             int window_y = 0)
12.19.2.3 gui_drawingarea_gtk2() [3/3]
seq64::gui\_drawingarea\_gtk2::gui\_drawingarea\_gtk2 (
             perform & a_perf,
             Gtk::Adjustment & a_hadjust,
             Gtk::Adjustment & a_vadjust,
             int window_x = 0,
             int window_y = 0)
12.19.2.4 ~gui_drawingarea_gtk2()
seq64::gui_drawingarea_gtk2::~gui_drawingarea_gtk2 ( ) [virtual]
12.19.3 Member Function Documentation
12.19.3.1 operator=()
gui_drawingarea_gtk2& seq64::gui_drawingarea_gtk2::operator= (
             const gui_drawingarea_gtk2 & ) [private]
12.19.3.2 window_x()
int seq64::gui_drawingarea_gtk2::window_x ( ) const [inline]
12.19.3.3 window_y()
int seq64::gui_drawingarea_gtk2::window_y ( ) const [inline]
12.19.3.4 current_x()
int seq64::gui_drawingarea_gtk2::current_x ( ) const [inline]
12.19.3.5 current_y()
int seq64::gui_drawingarea_gtk2::current_y ( ) const [inline]
```

```
12.19.3.6 drop_x()
int seq64::gui_drawingarea_gtk2::drop_x ( ) const [inline]

12.19.3.7 drop_y()
int seq64::gui_drawingarea_gtk2::drop_y ( ) const [inline]

12.19.3.8 force_draw()

virtual void seq64::gui_drawingarea_gtk2::force_draw ( ) [inline], [protected], [virtual]
This function forces a redraw. Some classes extend this function.
```

Reimplemented in seq64::seqroll, seq64::seqevent, and seq64::seqkeys.

```
12.19.3.9 perf()

perform& seq64::gui_drawingarea_gtk2::perf ( ) [inline], [protected]

12.19.3.10 clear_window()

void seq64::gui_drawingarea_gtk2::clear_window ( ) [inline], [protected]
```

One less need to access m_window directly.

Sets the attributes of a line to be drawn.

Parameters

12.19.3.11 set_line()

ls	Provides the Gtk-specific line style.	
width	Provides the width of the line to be drawn. It defaults to the most common value, 1.	

```
int x2, int y2) [inline], [protected]
```

x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
<i>y</i> 2	The y coordinate of the ending point.

12.19.3.13 draw_line() [2/6]

Parameters

С	The foreground color in which to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.19.3.14 draw_line_on_pixmap() [1/2]

```
void seq64::gui_drawingarea_gtk2::draw_line_on_pixmap (
    int x1,
    int y1,
    int x2,
    int y2 ) [inline], [protected]
```

Parameters

x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.19.3.15 draw_line_on_pixmap() [2/2]

С	The foreground color in which to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.19.3.16 draw_line() [3/6]

```
void seq64::gui_drawingarea_gtk2::draw_line (
    Glib::RefPtr< Gdk::Pixmap > & pixmap,
    int x1,
    int y1,
    int x2,
    int y2 ) [inline], [protected]
```

Parameters

pixmap	Provides the Gdk::Pixmap pointer needed to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.19.3.17 draw_line() [4/6]

Parameters

pixmap	Provides the Gdk::Drawable pointer needed to draw the line.
С	The foreground color in which to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.19.3.18 draw_line() [5/6]

```
void seq64::gui_drawingarea_gtk2::draw_line (
```

```
Glib::RefPtr< Gdk::Drawable > & drawable, int x1, int y1, int x2, int y2) [inline], [protected]
```

drawable	Provides the Gdk::Drawable pointer needed to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.19.3.19 draw_line() [6/6]

Parameters

drawable	Provides the Gdk::Drawable pointer needed to draw the line.
С	The foreground color in which to draw the line.
x1	The x coordinate of the starting point.
y1	The y coordinate of the starting point.
x2	The x coordinate of the ending point.
y2	The y coordinate of the ending point.

12.19.3.20 render_string()

```
void seq64::gui_drawingarea_gtk2::render_string (
    int x,
    int y,
    const std::string & s,
    font::Color color,
    bool invert = false ) [inline], [protected]
```

X	The x-coordinate of the origin.
У	The y-coordinate of the origin.
s	The string to be drawn.
color	The color with which to draw the string.
invert	If true, apply color inversion, if active. Defaults to false.

12.19.3.21 render_string_on_pixmap()

```
void seq64::gui_drawingarea_gtk2::render_string_on_pixmap (
    int x,
    int y,
    const std::string & s,
    font::Color color,
    bool invert = false ) [inline], [protected]
```

Parameters

х	The x-coordinate of the origin.
У	The y-coordinate of the origin.
s	The string to be drawn.
color	The color with which to draw the string.
invert	If true, apply color inversion, if active. Defaults to false.

12.19.3.22 draw_rectangle() [1/6]

Parameters

Х	The x-coordinate of the origin.
У	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults
	to true.

12.19.3.23 draw_rectangle() [2/6]

It adds setting the foreground color to the draw_rectangle() function.

С	Provides the foreground color to set.

X	The x-coordinate of the origin.
У	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults
	to true.

12.19.3.24 draw_rectangle() [3/6]

```
void seq64::gui_drawingarea_gtk2::draw_rectangle (
        Glib::RefPtr< Gdk::Drawable > & drawable,
        int x,
        int y,
        int lx,
        int ly,
        bool fill = true ) [inline], [protected]
```

Parameters

drawable	The object on which to draw the rectangle.
X	The x-coordinate of the origin.
У	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color).
	Defaults to true.

12.19.3.25 draw_rectangle() [4/6]

```
void seq64::gui_drawingarea_gtk2::draw_rectangle (
        Glib::RefPtr< Gdk::Drawable > & drawable,
        const Color & c,
        int x,
        int y,
        int lx,
        int ly,
        bool fill = true ) [protected]
```

It also supports setting the foreground color to the draw_rectangle() function.

We have a number of such functions: for the main window, for the main pixmap, and for any drawing surface. Is the small bit of conciseness worth it?

drawable	The surface on which to draw the box.
С	Provides the foreground color to set.
X	The x-coordinate of the origin.

У	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color).
	Defaults to true.

12.19.3.26 draw_rectangle() [5/6]

Parameters

pixmap	The object on which to draw the rectangle.
Х	The x-coordinate of the origin.
У	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color).
	Defaults to true.

12.19.3.27 draw_rectangle() [6/6]

It also supports setting the foreground color to the draw_rectangle() function.

We have a number of such functions: for the main window, for the main pixmap, and for any drawing surface. Is the small bit of conciseness worth it?

pixmap	The surface on which to draw the box.
С	Provides the foreground color to set.
Х	The x-coordinate of the origin.
У	The y-coordinate of the origin.

lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color).
	Defaults to true.

12.19.3.28 draw_rectangle_on_pixmap() [1/2]

```
void seq64::gui_drawingarea_gtk2::draw_rectangle_on_pixmap (
    int x,
    int y,
    int lx,
    int ly,
    bool fill = true ) [inline], [protected]
```

Parameters

Х	The x-coordinate of the origin.
У	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults
	to true.

12.19.3.29 draw_rectangle_on_pixmap() [2/2]

It adds setting the foreground color to the draw_rectangle() function.

С	Provides the foreground color to set.
Х	The x-coordinate of the origin.
У	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults
	to true.

12.19.3.30 draw_normal_rectangle_on_pixmap()

```
void seq64::gui_drawingarea_gtk2::draw_normal_rectangle_on_pixmap (
    int x,
    int y,
    int lx,
    int ly,
    bool fill = true ) [protected]
```

It uses Gtk to get the proper background styling for the rectangle.

Parameters

X	The x-coordinate of the origin.
У	The y-coordinate of the origin.
lx	The width of the box.
ly	The height of the box.
fill	If true, fill the rectangle with the current foreground color, as set by m_gc->set_foreground(color). Defaults
	to true.

12.19.3.31 draw_drawable()

```
void seq64::gui_drawingarea_gtk2::draw_drawable (
    int xsrc,
    int ysrc,
    int xdest,
    int ydest,
    int width,
    int height ) [inline], [protected]
```

12.19.3.32 scroll_hadjust()

This function is currently duplicated in the gui_drawingarea_gtk2 and gui_window_gtk2 modules.

Parameters

hadjust	Provides a reference to the adjustment object to be adjusted. Do we really need this to be a parameter? Why not just use the m_hadjust member? (Note that this member is not present in the similar gui_window_gtk2 class.)
step	Provides the step value to use for adjusting the horizontal scrollbar. If negative, the adjustment is
	leftward. If positive, the adjustment is rightward. It can be the value of m_hadjust->get_step_increment(), or provided especially to keep up with the progress bar.

12.19.3.33 scroll_vadjust()

```
void seq64::gui_drawingarea_gtk2::scroll_vadjust (
```

```
Gtk::Adjustment & vadjust,
double step ) [protected]
```

vadjust	Provides a reference to the adjustment object to be adjusted.
step	Provides the step value to use for adjusting the vertical scrollbar. If negative, the adjustment is upward. If positive, the adjustment is downward. It can be the value of
	m_vadjust->get_step_increment().

12.19.3.34 scroll_hset()

12.19.3.35 scroll_vset()

12.19.3.36 set_current_drop_x()

Parameters

```
x The x value to be set.
```

12.19.3.37 set_current_drop_y()

Parameters

```
y The y value to be set.
```

12.19.3.38 gtk_drawarea_init()

```
void seq64::gui_drawingarea_gtk2::gtk_drawarea_init ( ) [private]
```

```
12.19.3.39 on_realize()
```

```
void seq64::gui_drawingarea_gtk2::on_realize ( ) [protected]
```

It allocates any additional resources that weren't initialized in the constructor.

12.19.4 Field Documentation

12.19.4.1 m_gc

```
Glib::RefPtr<Gdk::GC> seq64::gui_drawingarea_gtk2::m_gc [protected]
```

12.19.4.2 m window

```
Glib::RefPtr<Gdk::Window> seq64::gui_drawingarea_gtk2::m_window [protected]
```

Wrapper functions with undecorated wrapper names are used for accessing this item. We hope to be able to hide this items completely some day.

12.19.4.3 m_vadjust

```
Gtk::Adjustment& seq64::gui_drawingarea_gtk2::m_vadjust [protected]
```

12.19.4.4 m_hadjust

```
Gtk::Adjustment& seq64::gui_drawingarea_gtk2::m_hadjust [protected]
```

12.19.4.5 m_pixmap

```
Glib::RefPtr<Gdk::Pixmap> seq64::gui_drawingarea_gtk2::m_pixmap [protected]
```

Wrapper functions with undecorated wrapper names are used for accessing this item. We hope to be able to hide this items completely some day.

12.19.4.6 m_background

```
Glib::RefPtr<Gdk::Pixmap> seq64::gui_drawingarea_gtk2::m_background [protected]
```

Our wrappers still leave this member exposed (giggle).

12.19.4.7 m_foreground

```
Glib::RefPtr<Gdk::Pixmap> seq64::gui_drawingarea_gtk2::m_foreground [protected]
```

Our wrappers still leave this member exposed.

```
12.19.4.8 m_mainperf
```

```
perform& seq64::gui_drawingarea_gtk2::m_mainperf [protected]
```

We could move this into yet another base class, since a number of classes don't need it. Probably not worth the effort at this time.

12.19.4.9 m_window_x

```
int seq64::gui_drawingarea_gtk2::m_window_x [protected]
```

Could make this constant, but some windows are resizable. Window width value.

12.19.4.10 m_window_y

```
int seq64::gui_drawingarea_gtk2::m_window_y [protected]
```

12.19.4.11 m_current_x

```
int seq64::gui_drawingarea_gtk2::m_current_x [protected]
```

Current mouse x value.

12.19.4.12 m_current_y

```
int seq64::gui_drawingarea_gtk2::m_current_y [protected]
```

12.19.4.13 m_drop_x

```
int seq64::gui_drawingarea_gtk2::m_drop_x [protected]
```

Provides the x and y value of where the dragging started. Current mouse x-drop value.


12.19.4.14 m_drop_y

```
int seq64::gui_drawingarea_gtk2::m_drop_y [protected]
```

12.20 seq64::gui_palette_gtk2 Class Reference

Implements a stock palette of Gdk::Color elements.

Inheritance diagram for seq64::gui_palette_gtk2:



Public Member Functions

• gui_palette_gtk2 ()

Principal constructor.

~gui_palette_gtk2 ()

Provides a destructor to delete allocated objects.

· const Color & line color () const

'Getter' function for member m_line_color Provides an experimental way to change some line colors from black to something else.

const Color & progress_color () const

'Getter' function for member m_progress_color Provides an experimental way to change the progress line color from black to something else.

· const Color & black () const

'Getter' function for member m_black Although these color getters return static values (if so compiled), these colors are used only in the window and drawing-area classes, so no need to make these functions static.

· const Color & dark_red () const

'Getter' function for member m_dk_red

· const Color & dark_green () const

'Getter' function for member m_dk_green

• const Color & dark_orange () const

'Getter' function for member m_dk_orange

• const Color & dark_blue () const

'Getter' function for member m_dk_blue

const Color & dark_magenta () const

'Getter' function for member m_dk_magenta

const Color & dark_cyan () const

'Getter' function for member m_dk_cyan

• const Color & white () const

'Getter' function for member m_white

const Color & grey () const

'Getter' function for member m_grey

const Color & dark_grey () const

'Getter' function for member m_dk_grey

const Color & light_grey () const

'Getter' function for member m_lt_grey

· const Color & red () const

'Getter' function for member m_red

• const Color & orange () const

'Getter' function for member m_orange

const Color & yellow () const

'Getter' function for member m_yellow

· const Color & green () const

'Getter' function for member m_green

const Color & blue () const

'Getter' function for member m_blue

· const Color & black_paint () const

'Getter' function for member m_blk_paint

const Color & white_paint () const

'Getter' function for member m_wht_paint

· const Color & black key () const

'Getter' function for member m blk key

• const Color & white_key () const

'Getter' function for member m_wht_key

const Color & bg_color () const

'Getter' function for member m_bg_color

void bg_color (const Color &c)

'Setter' function for member m_bg_color

· const Color & fg color () const

'Getter' function for member m_fg_color

void fg_color (const Color &c)

'Setter' function for member m fg color

Static Public Member Functions

static void load_inverse_palette (bool inverse=true)

Provides an alternate color palette, somewhat constrained by the colors in the font bitmaps.

• static bool is_inverse ()

Indicates if the inverse color palette is loaded.

Protected Types

· typedef Gdk::Color Color

Provides a type for the color object.

Private Attributes

· Color m_line_color

Provides the line color.

• Color m_progress_color

Provides the progress bar color.

• Color m_bg_color

The current background color.

• Color m_fg_color

The current foreground color.

Static Private Attributes

• static bool m_is_inverse

Flags the presense of the inverse color palette.

· static const Color m black

Provides the black color.

· static const Color m_dk_red

Provides a blood-red color.

static const Color m_dk_green

Provides a dark green color.

static const Color m dk orange

Provides a dark orange color.

static const Color m_dk_blue

Provides the dark blue color.

static const Color m_dk_magenta

Provides the dark cyan color.

• static const Color m_dk_cyan

Provides the dark cyan color.

• static const Color m_red

Provides the red color.

• static const Color m_white

Provides the white color.

• static const Color m_orange

Provides the orange color.

• static const Color m_yellow

Provides the yellow color.

• static const Color m_green

Provides the green color.

• static const Color m_blue

Provides the blue color.

static Color m_grey

Provides the grey color.

static Color m_dk_grey

Provides the dark grey color.

static Color m_lt_grey

Provides the light grey color.

· static Color m blk paint

An invertible black color.

• static Color m_wht_paint

An invertible white color.

static Color m_blk_key

Provides the color of a black key.

· static Color m wht key

Provides the color of a white key.

12.20.1 Detailed Description

Note that this class must be derived from Gtk::DrawingArea (or Gtk::Widget) in order to get access to the get_
default_colormap() function used in the constructor.

12.20.2 Member Typedef Documentation

12.20.2.1 Color

```
typedef Gdk::Color seq64::gui_palette_gtk2::Color [protected]
```

The following uses are made of each color:

- Black. The background color of armed patterns. The color of most lines in the user interface, including the main grid lines. The default color of progress lines and text.
- White. The default background color of just about everything drawn in the application.
- · Grey. The color of minor grid lines and the markers for the currently-selected scale.
- Dark grey. The color of some grid lines, and the background of a queued pattern slot.
- Light grey. The color of some grid lines.
- · Red. The optional color of progress bars.
- · Orange. The fill-in color for selected notes and events.
- Dark orange. The color of selected event data lines and the color of the selection box for events to be pasted.
- Yellow. The background of the pattern and name slots for empty patterns. The text color for selected empty pattern slots.
- · Green. Not yet used.
- · Blue. Not yet used.
- Dark cyan. The background color of muted patterns currently in edit, or the pattern that contains the original data for an imported SMF 0 song. The text color of an unmuted pattern currently in edit. These colors apply to the pattern editor and the song editor. The color of the selected background pattern in the song editor.
- · Line color. The generic line color, meant for expansion. Currently black.
- Progress color. The progress line color. Black by default, but can be set to red.
- · Background color. The currently-in-use background color. Can vary a lot when a pixmap is being redrawn.
- Foreground color. The currently-in-use foreground color. Can vary a lot when a pixmap is being redrawn.

12.20.3 Constructor & Destructor Documentation

```
12.20.3.1 gui_palette_gtk2()
```

```
seq64::gui_palette_gtk2::gui_palette_gtk2 ( )
```

In the constructor one can only allocate colors; get_window() returns 0 because this window has not yet been realized. Also note that the possible color names that can be used are found in /usr/share/X11/rgb.txt.

```
12.20.3.2 ~gui_palette_gtk2()
```

```
seq64::gui\_palette\_gtk2::\sim gui\_palette\_gtk2 ( )
```

12.20.4 Member Function Documentation

12.20.4.1 load_inverse_palette()

Inverse is not a complete inverse. It is more like a "night" mode. However, there are still some bright colors even in this mode. Some colors, such as the selection color (orange) are the same in either mode.

Parameters

```
inverse If true, load the alternate palette. Otherwise, load the default palette.
```

12.20.4.2 is_inverse()

```
static bool seq64::gui_palette_gtk2::is_inverse ( ) [inline], [static]
```

12.20.4.3 line_color()

```
const Color& seq64::gui_palette_gtk2::line_color ( ) const [inline]
```

Might eventually be selectable from the "user" configuration file

12.20.4.4 progress_color()

```
const Color& seq64::gui_palette_gtk2::progress_color ( ) const [inline]
```

Now selectable from the "user" configuration file.

```
12.20.4.5 black()
const Color& seq64::gui_palette_gtk2::black ( ) const [inline]
12.20.4.6 dark_red()
const Color& seq64::gui_palette_gtk2::dark_red ( ) const [inline]
12.20.4.7 dark_green()
const Color& seq64::gui_palette_gtk2::dark_green ( ) const [inline]
12.20.4.8 dark_orange()
const Color& seq64::gui_palette_gtk2::dark_orange ( ) const [inline]
12.20.4.9 dark_blue()
const Color& seq64::gui_palette_gtk2::dark_blue ( ) const [inline]
12.20.4.10 dark_magenta()
const Color& seq64::gui_palette_gtk2::dark_magenta ( ) const [inline]
12.20.4.11 dark_cyan()
const Color& seq64::gui_palette_gtk2::dark_cyan ( ) const [inline]
12.20.4.12 white()
const Color& seq64::gui_palette_gtk2::white ( ) const [inline]
12.20.4.13 grey()
const Color& seq64::gui_palette_gtk2::grey ( ) const [inline]
12.20.4.14 dark_grey()
const Color& seq64::gui_palette_gtk2::dark_grey ( ) const [inline]
```

```
12.20.4.15 light_grey()
const Color& seq64::gui_palette_gtk2::light_grey ( ) const [inline]
12.20.4.16 red()
const Color& seq64::gui_palette_gtk2::red ( ) const [inline]
12.20.4.17 orange()
const Color& seq64::gui_palette_gtk2::orange ( ) const [inline]
12.20.4.18 yellow()
const Color& seq64::gui_palette_gtk2::yellow ( ) const [inline]
12.20.4.19 green()
const Color& seq64::gui_palette_gtk2::green ( ) const [inline]
12.20.4.20 blue()
const Color& seq64::gui_palette_gtk2::blue ( ) const [inline]
12.20.4.21 black_paint()
const Color& seq64::gui_palette_gtk2::black_paint ( ) const [inline]
12.20.4.22 white_paint()
const Color& seq64::gui_palette_gtk2::white_paint ( ) const [inline]
12.20.4.23 black_key()
const Color& seq64::gui_palette_gtk2::black_key ( ) const [inline]
12.20.4.24 white_key()
const Color& seq64::gui_palette_gtk2::white_key ( ) const [inline]
```

```
12.20.4.25 bg_color() [1/2]
const Color& seq64::gui_palette_gtk2::bg_color ( ) const [inline]
12.20.4.26 bg_color() [2/2]
void seq64::gui_palette_gtk2::bg_color (
             const Color & c ) [inline]
12.20.4.27 fg_color() [1/2]
const Color& seq64::gui_palette_gtk2::fg_color ( ) const [inline]
12.20.4.28 fg_color() [2/2]
void seq64::gui\_palette\_gtk2::fg\_color (
             const Color & c ) [inline]
12.20.5 Field Documentation
12.20.5.1 m_is_inverse
bool seq64::gui_palette_gtk2::m_is_inverse [static], [private]
By default, the inverse color palette is not loaded.
12.20.5.2 m_black
const STATIC_COLOR seq64::gui_palette_gtk2::m_black [static], [private]
12.20.5.3 m_dk_red
const STATIC_COLOR seq64::gui_palette_gtk2::m_dk_red [static], [private]
12.20.5.4 m_dk_green
const STATIC_COLOR seq64::gui_palette_gtk2::m_dk_green [static], [private]
12.20.5.5 m_dk_orange
const STATIC_COLOR seq64::gui_palette_gtk2::m_dk_orange [static], [private]
```


```
12.20.5.6 m_dk_blue
const STATIC_COLOR seq64::gui_palette_gtk2::m_dk_blue [static], [private]
12.20.5.7 m_dk_magenta
const STATIC_COLOR seq64::gui_palette_gtk2::m_dk_magenta [static], [private]
12.20.5.8 m_dk_cyan
const STATIC_COLOR seq64::gui_palette_gtk2::m_dk_cyan [static], [private]
12.20.5.9 m_red
const STATIC_COLOR seq64::gui_palette_gtk2::m_red [static], [private]
12.20.5.10 m_white
const STATIC_COLOR seq64::gui_palette_gtk2::m_white [static], [private]
12.20.5.11 m_orange
const STATIC_COLOR seq64::gui_palette_gtk2::m_orange [static], [private]
12.20.5.12 m_yellow
const STATIC_COLOR seq64::gui_palette_gtk2::m_yellow [static], [private]
12.20.5.13 m_green
const STATIC_COLOR seq64::gui_palette_gtk2::m_green [static], [private]
12.20.5.14 m_blue
const STATIC_COLOR seq64::gui_palette_gtk2::m_blue [static], [private]
12.20.5.15 m_grey
STATIC_COLOR seq64::gui_palette_gtk2::m_grey [static], [private]
```

```
12.20.5.16 m_dk_grey
STATIC_COLOR seq64::gui_palette_gtk2::m_dk_grey [static], [private]
12.20.5.17 m_lt_grey
STATIC_COLOR seq64::gui_palette_gtk2::m_lt_grey [static], [private]
12.20.5.18 m_blk_paint
STATIC_COLOR seq64::gui_palette_gtk2::m_blk_paint [static], [private]
12.20.5.19 m_wht_paint
{\tt STATIC\_COLOR} \ \ {\tt seq64::gui\_palette\_gtk2::m\_wht\_paint} \quad [{\tt static}], \ [{\tt private}]
12.20.5.20 m_blk_key
STATIC_COLOR seq64::gui_palette_gtk2::m_blk_key [static], [private]
12.20.5.21 m_wht_key
STATIC_COLOR seq64::gui_palette_gtk2::m_wht_key [static], [private]
12.20.5.22 m_line_color
Color seq64::gui_palette_gtk2::m_line_color [private]
12.20.5.23 m_progress_color
Color seq64::gui_palette_gtk2::m_progress_color [private]
12.20.5.24 m bg color
Color seq64::gui_palette_gtk2::m_bg_color [private]
12.20.5.25 m_fg_color
Color seq64::gui_palette_gtk2::m_fg_color [private]
```

12.21 seq64::gui_window_gtk2 Class Reference

This class supports a basic interface for Gtk::Window-derived objects.

Inheritance diagram for seq64::gui window gtk2:



Public Member Functions

• gui_window_gtk2 (perform &p, int window_x=0, int window_y=0)

Principal constructor, has a reference to the all-important perform object.

• virtual \sim gui_window_gtk2 ()

This rote constructor does nothing.

Protected Member Functions

• perform & perf ()

'Getter' function for member m_mainperf

· virtual void quit ()

Provides "quit" functionality that WE HAVE OVERLOOKED!!! At some point we need to rectify this situation, probably for the sake of session support.

int redraw_period_ms () const

'Getter' function for member m_redraw_period_ms

· bool is_realized () const

'Getter' function for member m_is_realized

void scroll_hadjust (Gtk::Adjustment &hadjust, double step)

This function provides optimization for the on_scroll_event() functions, and should provide support for having the seqedit/seqroll/seqtime/seqdata panes follow the scrollbar, in a future upgrade.

void scroll_vadjust (Gtk::Adjustment &vadjust, double step)

This function is the vertical version of scroll hadjust().

void scroll_hset (Gtk::Adjustment &hadjust, double value)

This function is the horizontal scroll setter.

void scroll_vset (Gtk::Adjustment &vadjust, double value)

This function is the vertical scroll setter.

• void on_realize ()

This callback function calls the base-class on_realize() function, and sets the m_is_realized flag.

Private Attributes

• perform & m_mainperf

The master object, sort of a sequence buss for all of the sequence.

• int m_window_x

Window sizes.

• int m_window_y

The height of the window.

• int m_redraw_period_ms

Provides the timer period for the eventedit timer, used to determine the rate of redrawing.

· bool m is realized

Indicates if on_realize() has been called.

12.21.1 Constructor & Destructor Documentation

12.21.1.1 gui_window_gtk2()

Note

We've collected the redraw timeouts into a base-class member. Most were valued at c_redraw_ms (40 ms), but mainwnd used 25 ms, so beware. We will eventually make this a user-interface parameter.

Parameters

р	Refers to the main performance object.
window⇔	The width of the window.
_x	
window⊷	The height of the window.
_y	

```
12.21.1.2 ∼gui_window_gtk2()
seq64{::}gui\_window\_gtk2{::}{\sim}gui\_window\_gtk2 \text{ ( ) } [virtual]
12.21.2 Member Function Documentation
12.21.2.1 perf()
perform& seq64::gui_window_gtk2::perf ( ) [inline], [protected]
12.21.2.2 quit()
virtual void seq64::gui_window_gtk2::quit ( ) [inline], [protected], [virtual]
12.21.2.3 redraw_period_ms()
int seq64::gui_window_gtk2::redraw_period_ms ( ) const [inline], [protected]
12.21.2.4 is_realized()
bool seq64::gui_window_gtk2::is_realized ( ) const [inline], [protected]
12.21.2.5 scroll_hadjust()
void seq64::gui_window_gtk2::scroll_hadjust (
             Gtk::Adjustment & hadjust,
              double step ) [protected]
```

This function is currently duplicated in the gui_drawingarea_gtk2 and gui_window_gtk2 modules.

Parameters

hadjust	Provides a reference to the adjustment object to be adjusted.
step	Provides the step value to use for adjusting the horizontal scrollbar. If negative, the adjustment is
	leftward. If positive, the adjustment is rightward. It can be the value of m_hadjust->get_step_increment(), or provided especially to keep up with the progress bar.

12.21.2.6 scroll_vadjust()

vadjust	Provides a reference to the adjustment object to be adjusted.	
step	Provides the step value to use for adjusting the vertical scrollbar. If greater than 0, the movement is	
	downward. If less than zero, the movement is upward.	

12.21.2.7 scroll_hset()

Parameters

hadjust	Provides a reference to the adjustment object to be set. It is clamped as necessary.
value	Provides the value to use for setting the horizontal scrollbar.

12.21.2.8 scroll_vset()

Parameters

vadjust	Provides a reference to the vertical adjustment object to be set. It is clamped as necessary.
value	Provides the value to use for setting the vertical scrollbar.

12.21.2.9 on_realize()

```
void seq64::gui_window_gtk2::on_realize ( ) [protected]
```

12.21.3 Field Documentation

12.21.3.1 m_mainperf

```
perform& seq64::gui_window_gtk2::m_mainperf [private]
```

And a whole lot more than that.

```
12.21.3.2 m_window_x
```

```
int seq64::gui_window_gtk2::m_window_x [private]
```

Could make this constant, but some windows are resizable. The width of the window.

12.21.3.3 m_window_y

```
int seq64::gui_window_gtk2::m_window_y [private]
```

12.21.3.4 m_redraw_period_ms

```
int seq64::gui_window_gtk2::m_redraw_period_ms [private]
```

This is currently hardwired to 40 ms in Linux, and 20 ms in Windows. Note that mainwind used 25 ms.

12.21.3.5 m_is_realized

```
bool seq64::gui_window_gtk2::m_is_realized [private]
```

In some cases, we don't want to draw in objects that haven't yet appeared, otherwise crashes occur.

12.22 seq64::jack_assistant Class Reference

This class provides the performance mode JACK support.

Public Member Functions

jack_assistant (perform &parent, int bpminute=SEQ64_DEFAULT_BPM, int ppqn=SEQ64_USE_DEFAUL
 — T_PPQN, int bpm=SEQ64_DEFAULT_BEATS_PER_MEASURE, int beatwidth=SEQ64_DEFAULT_BEAT
 — WIDTH)

This constructor initializes a number of member variables, some of them public!

• \sim jack_assistant ()

The destructor doesn't need to do anything yet.

· perform & parent ()

'Getter' function for member m_jack_parent Needed for external callbacks.

• const perform & parent () const

'Getter' function for member m_jack_parent, const version

bool is_running () const

'Getter' function for member m_jack_running

• bool is_master () const

'Getter' function for member m_jack_master

int get_ppqn () const

'Getter' function for member m_ppqn

• int get_beat_width () const

'Getter' function for member m_beat_width

void set_beat_width (int bw)

'Setter' function for member m_beat_width

int get_beats_per_measure () const

'Getter' function for member m_beats_per_measure

void set beats per measure (int bpm)

'Setter' function for member m_beats_per_measure

int get_beats_per_minute () const

'Getter' function for member m_beats_per_minute

void set_beats_per_minute (int bpminute)

'Setter' function for member m_beats_per_minute For the future, changing the BPM (beats/minute) internally.

• jack_transport_state_t transport_state () const

'Getter' function for member m_jack_transport_state

• bool transport_not_starting () const

Returns true if the JACK transport state is not JackTransportStarting.

· bool init ()

Initializes JACK support.

• bool deinit ()

Tears down the JACK infrastructure.

bool session event ()

Writes the MIDI file named "< jack session dir>-file.mid" using a midifile object, quits if told to by JACK, and can free the JACK session event.

• void start ()

If JACK is supported, starts the JACK transport.

void stop ()

If JACK is supported, stops the JACK transport.

void position (bool state, midipulse tick=0)

If JACK is supported and running, sets the position of the transport to the new frame number, frame 0.

bool output (jack_scratchpad &pad)

Performance output function for JACK, called by the perform function of the same name.

void set_ppqn (int ppqn)

'Setter' function for member m_ppqn For the future, changing the PPQN internally.

double get_jack_tick () const

'Getter' function for member m_jack_tick

const jack_position_t & get_jack_pos () const

'Getter' function for member m_jack_pos

- void toggle_jack_mode ()
- void set_jack_mode (bool mode)
- bool get_jack_mode () const

'Getter' function for member m_toggle_jack Seems misnamed.

• midipulse get_jack_stop_tick () const

'Getter' function for member m_jack_stop_tick

void set_jack_stop_tick (long tick)

'Setter' function for member m_jack_stop_tick

• jack_nframes_t jack_frame_rate () const

'Getter' function for member m_jack_frame_rate

bool get_follow_transport () const

 ${\it 'Getter' function for member m_follow_transport}$

void set_follow_transport (bool aset)

'Setter' function for member m_follow_transport

void toggle_follow_transport ()

'Setter' function for member m_follow_transport

• bool toggle song start mode ()

'Setter' function for member parent().toggle_song_start_mode()

bool song_start_mode () const

'Getter' function for member parent().song_start_mode()

· void set start from perfedit (bool start)

'Setter' function for member parent().start_from_perfedit()

• jack_client_t * client () const

'Getter' function for member m_jack_client

· const std::string & client_name () const

'Getter' function for member m jack client name

const std::string & client_uuid () const

'Getter' function for member m_jack_client_uuid

Private Member Functions

void set_jack_running (bool flag)

'Setter' function for member m_jack_running

· double tick_multiplier () const

Convenience function for internal use.

bool info_message (const std::string &msg)

Common-code for console messages.

bool error_message (const std::string &msg)

Common-code for error messages.

• jack client t * client open (const std::string &clientname)

A more full-featured initialization for a JACK client, which is meant to be called by the init() function.

void get_jack_client_info ()

Tries to obtain the best information on the JACK client and the UUID assigned to this client.

· void show statuses (unsigned bits)

Loops through the full set of JACK bits, showing the information for any bits that are set in the given parameter.

void show_position (const jack_position_t &pos) const

Shows a one-line summary of a JACK position structure.

int sync (jack_transport_state_t state=(jack_transport_state_t)(-1))

A helper function for syncing up with JACK parameters.

· void set position (midipulse currenttick)

Provides the code that was effectively commented out in the perform::position_jack() function.

Private Attributes

· perform & m jack parent

Provides the perform object that needs this JACK assistant/scratchpad class.

jack_client_t * m_jack_client

Provides a handle into JACK, so that the application, as a JACK client, can issue commands and retrieve status information from JACK.

• std::string m_jack_client_name

A new member to hold the actual name of the client assigned by JACK.

• std::string m_jack_client_uuid

A new member to hold the actual UUID of the client assigned by JACK.

jack_nframes_t m_jack_frame_current

Holds the current frame number obtained from JACK transport, via a call to jack_get_current_transport_frame().

· jack nframes t m jack frame last

Holds the last frame number we got from JACK, so that progress can be tracked.

jack_position_t m_jack_pos

Provides positioning information on JACK playback.

jack_transport_state_t m_jack_transport_state

Holds the JACK transport state.

jack_transport_state_t m_jack_transport_state_last

Holds the last JACK transport state.

· double m_jack_tick

The tick/pulse value derived from the current frame number, the ticks/beat value, the beats/minute value, and the frame rate.

jack_session_event_t * m_jsession_ev

Provides a kind of handle to the JACK session manager.

bool m_jack_running

Indicates if JACK Sync has been enabled successfully.

bool m_jack_master

Indicates if JACK Sync has been enabled successfully, with the application running as JACK Master.

• jack_nframes_t m_jack_frame_rate

Holds the current frame rate.

• bool m_toggle_jack

Ostensibly a toggle, the functions that access this member are called "jack_mode" functions.

midipulse m_jack_stop_tick

Used in jack process_callback() to reposition when JACK transport is not rolling or starting.

· bool m follow transport

TBD.

• int m_ppqn

Holds the global PPQN value for the Sequencer64 session.

int m_beats_per_measure

Holds the song's beats/measure value for using in setting JACK position.

int m_beat_width

Holds the song's beat width value (denominator of the time signature) for using in setting JACK position.

• int m_beats_per_minute

Holds the song's beats/minute (BPM) value for using in setting JACK position.

Static Private Attributes

static jack_status_pair_t sm_status_pairs []

Pairs the JACK status bits with human-readable descriptions of each one.

Friends

- int jack_process_callback (jack_nframes_t nframes, void *arg)
- void jack_shutdown_callback (void *arg)

This callback is to shut down JACK by clearing the jack_assistant :: m_jack_running flag.

int jack_sync_callback (jack_transport_state_t state, jack_position_t *pos, void *arg)

Global functions for JACK support and JACK sessions.

void jack_timebase_callback (jack_transport_state_t state, jack_nframes_t nframes, jack_position_t *pos, int new_pos, void *arg)

The JACK timebase function defined here sets the JACK position structure.

void jack session callback (jack session event t *ev, void *arg)

Set the m_jsession_ev (event) value of the perform object.

12.22.1 Constructor & Destructor Documentation

12.22.1.1 jack_assistant()

```
seq64::jack_assistant::jack_assistant (
    perform & parent,
    int bpminute = SEQ64_DEFAULT_BPM,
    int ppqn = SEQ64_USE_DEFAULT_PPQN,
    int bpm = SEQ64_DEFAULT_BEATS_PER_MEASURE,
    int beatwidth = SEQ64_DEFAULT_BEAT_WIDTH )
```

Note that the perform object currently calls jack_assistant::init(), but that call could be made here instead.

Parameters

parent	Provides a reference to the main perform object that needs to control JACK event.
bpminute	The beats/minute to set up JACK to use (applies to Master setup).
ppqn	The parts-per-quarter-note setting in force for the present tune.
bpm	The beats/measure (time signature numerator) in force for the present tune.
beatwidth	The beat-width (time signature denominator) in force for the present tune.

12.22.1.2 ∼jack_assistant()

```
seq64::jack_assistant::~jack_assistant ( )
```

The perform object currently calls jack_assistant::deinit(), but that call could be made here instead.

12.22.2 Member Function Documentation

```
12.22.2.1 parent() [1/2]

perform& seq64::jack_assistant::parent ( ) [inline]

12.22.2.2 parent() [2/2]

const perform& seq64::jack_assistant::parent ( ) const [inline]

12.22.2.3 is_running()

bool seq64::jack_assistant::is_running ( ) const [inline]

12.22.2.4 is_master()

bool seq64::jack_assistant::is_master ( ) const [inline]
```

```
12.22.2.5 get_ppqn()
int seq64::jack_assistant::get_ppqn ( ) const [inline]
12.22.2.6 get_beat_width()
int seq64::jack_assistant::get_beat_width ( ) const [inline]
12.22.2.7 set_beat_width()
void seq64::jack_assistant::set_beat_width (
             int bw ) [inline]
Parameters
      Provides the beat-width (denominator of the time signature) value to set.
12.22.2.8 get_beats_per_measure()
int seq64::jack_assistant::get_beats_per_measure ( ) const [inline]
12.22.2.9 set_beats_per_measure()
void seq64::jack_assistant::set_beats_per_measure (
             int bpm ) [inline]
Parameters
        Provides the beats/measure (numerator of the time signature) value to set.
 bpm
12.22.2.10 get_beats_per_minute()
int seq64::jack_assistant::get_beats_per_minute ( ) const [inline]
12.22.2.11 set_beats_per_minute()
```

We should consider adding validation. However, perform::set_beats_per_minute() does validate already.

Parameters

bpminute Provides the beats/minute value to set.

void seq64::jack_assistant::set_beats_per_minute (
 int bpminute) [inline]

12.22.2.12 transport_state()

```
jack_transport_state_t seq64::jack_assistant::transport_state ( ) const [inline]

12.22.2.13 transport_not_starting()

bool seq64::jack_assistant::transport_not_starting ( ) const [inline]

12.22.2.14 init()
```

bool seq64::jack_assistant::init ()

Then we become a new client of the JACK server.

A sync callback is needed for polling of slow-sync clients. But seq24/sequencer64 are not slow-sync clients. We don't really need to be a slow-sync client, as far as we can tell. We can't get JACK working exactly the way it does in seq24 without the callback in place. Plus, it does things important to the setup of JACK. So now this setup is permanent.

Jack transport settings:

```
There are three settings: On, Master, and Master Conditional. Currently, they can all be selected in the user-interface's File / Options / JACK/LASH page. We really want only the proper combinations to be set, for clarity (the user-interface now takes care of this. We need to initialize if any of them are set, and the rc_settings::with_jack() function tells us that.
```

jack_set_process_callback() patch:

```
Implemented first patch from freddix/seq24 GitHub project, to fix JACK transport. One line of code. Well, we added some error-checking. :-) Found some old notes on the Web the this patch really only works (to prevent seq24 freeze) if seq24 is set as JACK Master, or if another client application, such as Qtractor, is running as JACK Master (and then seq24 will apparently follow it).
```

STAZED: The call to jack_timebase_callback() to supply jack with BBT, etc would occasionally fail when the *pos information had zero or some garbage in the pos.frame_rate variable. This would occur when there was a rapid change of frame position by another client... i.e. gjackctl. From the jack API:

"pos address of the position structure for the next cycle; pos->frame will be its frame number. If new_pos is FALSE, this structure contains extended position information from the current cycle. If TRUE, it contains whatever was set by the requester. The timebase_callback's task is to update the extended information here."

The "If TRUE" line seems to be the issue. It seems that qjackctl does not always set pos.frame_rate so we get garbage and some strange BBT calculations that display in qjackctl. So we need to set it here and just use m_\iff jack_frame_rate for calculations instead of pos.frame_rate.

Returns

Returns true if JACK is now considered to be running (or if it was already running.)

12.22.2.15 deinit()

```
bool seq64::jack_assistant::deinit ( )
```

Returns

Returns the value of m_jack_running, which should be false.

12.22.2.16 session_event()

```
bool seq64::jack_assistant::session_event ( )
```

ca 2015-07-24 Just a note: The OMA (OpenMandrivaAssociation) patch was already applied to seq24 v.0.9.2. It put quotes around the –file argument. However, the –file option doesn't work, so let's change that line.

```
sequencer64 --file \"${SESSION_DIR}file.mid\" --jack_session_uuid
```

Why are we using a Glib::ustring here? Convenience. But with C++11, we could use a lexical_cast<>. No more ustring, baby! It doesn't really matter; this function can call Gtk::Main::quit(), via the parent's gui().quit() function.

Returns

Always returns false.

12.22.2.17 start()

```
void seq64::jack_assistant::start ( )
```

This function assumes that m_jack_client is not null, if m_jack_running is true.

Found this note in the Hydrogen code:

```
When jack_transport_start() is called, it takes effect from the next processing cycle. The location info from the timebase_master, if there is one, will not be available until the _next_ next cycle. The code must therefore wait one cycle before syncing up with timebase_master.
```

12.22.2.18 stop()

```
void seq64::jack_assistant::stop ( )
```

This function assumes that m_jack_client is not null, if m_jack_running is true.

12.22.2.19 position()

This new position takes effect in two process cycles. If there are slow-sync clients and the transport is already rolling, it will enter the JackTransportStarting state and begin invoking their sync_callbacks until ready. This function is realtime-safe.

```
http://jackaudio.org/files/docs/html/transport-design.html
```

This position() function is called via perform::position_jack() in the mainwnd, perfedit, perfroll, and seqroll graphical user-interface support objects.

The code that was disabled sets the current tick to 0 or, if state was true, to the leftmost tick (which is probably the position of the L marker). The current tick is then converted to a frame number, and then we locate the transport to that position. We're going to enable this code, but make it dependent on a new boolean parameter that defaults to false, in anticipation of trying it out later.

Stazed:

```
The jack_frame calculation is all that is needed to change JACK position The BBT calc can be sent but will be overridden by the first call to jack_timebase_callback() of any Master set. If no Master is set, then the BBT will display the new position but will not change even if the transport is rolling. There is no need to send BBT on position change - the fact that the function jack_transport_locate() exists and only uses the frame position is proof that BBT is not needed! Upon further reflection, why not send BBT? Because other programs do not... let's follow convention. The below calculation for jack_transport_locate(), works, is simpler and does not send BBT. The calculation for jack_transport_reposition() will be commented out again. The BBT call to jack_BBT_position() is not necessary to change jack position!
```

Note that there are potentially a couple of divide-by-zero opportunities in this function.

Parameters

songmode	True if the caller wants to position while in Song mode.
tick	If using Song mode for this call then this value is set as the "current tick" value. If it's value is bad
	(SEQ64_NULL_MIDIPULSE), then this parameter is set to 0 before being used.

12.22.2.20 output()

This code comes from perform::output_func() from seq24.

Note

Follow up on this note found "out there": "Maybe I'm wrong but if I understood correctly, recent jack1 transport no longer goes into Jack_Transport_Starting state before going to Jack_Transport_Rolling (this was deliberately dropped), but seq24 currently needs this to start off with JACK transport." On the other hand, some people have no issues. This may have been due to the lack of m_jack_pos initialization.

Stazed:

Another note about JACK.... If another JACK client is supplying tempo/BBT info that is different from seq42 (as Master), the perfroll grid will be incorrect. Perfroll uses internal temp/BBT and cannot update on the fly. Even if seq42 could support tempo/BBT changes, all info would have to be available before the transport start, to work. For this reason, the tempo/BBT info will be plugged from the seq42 internal settings here... always. This is the method used by probably all other JACK clients with some sort of time-line. The JACK API indicates that BBT is optional and AFIK, other sequencers only use frame & frame_rate from JACK for internal calculations. The tempo and BBT info is always internal. Also, if there is no Master set, then we would need to plug it here to follow the JACK frame anyways.

Parameters

pad

Provide a JACK scratchpad for sharing certain items between the perform object and the jack_assistant object.

Returns

Returns true if JACK is running.

12.22.2.21 set_ppqn()

We should consider adding validation. But it is used by perform.

Parameters

ppqn Provides the PPQN value to set.

12.22.2.22 get_jack_tick()

```
double seq64::jack_assistant::get_jack_tick ( ) const [inline]
```

12.22.2.23 get_jack_pos()

```
12.22.2.24 toggle_jack_mode()
void seq64::jack_assistant::toggle_jack_mode ( ) [inline]
12.22.2.25 set_jack_mode()
void seq64::jack_assistant::set_jack_mode (
             bool mode ) [inline]
12.22.2.26 get_jack_mode()
bool seq64::jack_assistant::get_jack_mode ( ) const [inline]
12.22.2.27 get_jack_stop_tick()
midipulse seq64::jack_assistant::get_jack_stop_tick ( ) const [inline]
12.22.2.28 set_jack_stop_tick()
void seq64::jack_assistant::set_jack_stop_tick (
             long tick ) [inline]
12.22.2.29 jack_frame_rate()
jack_nframes_t seq64::jack_assistant::jack_frame_rate ( ) const [inline]
12.22.2.30 get_follow_transport()
bool seq64::jack_assistant::get_follow_transport ( ) const [inline]
12.22.2.31 set_follow_transport()
void seq64::jack_assistant::set_follow_transport (
             bool aset ) [inline]
12.22.2.32 toggle_follow_transport()
void seq64::jack_assistant::toggle_follow_transport ( ) [inline]
12.22.2.33 toggle_song_start_mode()
bool seq64::jack_assistant::toggle_song_start_mode ( )
```

```
12.22.2.34 song_start_mode()
bool seq64::jack_assistant::song_start_mode ( ) const
12.22.2.35 set_start_from_perfedit()
void seq64::jack_assistant::set_start_from_perfedit (
             bool start )
12.22.2.36 client()
jack_client_t* seq64::jack_assistant::client ( ) const [inline]
12.22.2.37 client_name()
const std::string& seq64::jack_assistant::client_name ( ) const [inline]
12.22.2.38 client_uuid()
const std::string& seq64::jack_assistant::client_uuid ( ) const [inline]
12.22.2.39 set_jack_running()
void seq64::jack_assistant::set_jack_running (
              bool flag ) [inline], [private]
Parameters
       Provides the is-running value to set.
 flaa
12.22.2.40 tick_multiplier()
double seq64::jack_assistant::tick_multiplier ( ) const [inline], [private]
Should we change 4.0 to a member value? What does it mean?
Returns
     Returns the multiplier to convert a JACK tick value according to the PPQN, ticks/beat, and beat-type settings.
12.22.2.41 info_message()
bool seq64::jack_assistant::info_message (
              const std::string & msg ) [private]
Adds markers and a newline.
```

msg The message to print, sans the newline.

Returns

Returns true.

12.22.2.42 error_message()

Adds markers, and sets m_jack_running to false.

Parameters

msg The message to print, sans the newline.

Returns

Returns false for convenience/brevity in setting function return values.

12.22.2.43 client_open()

Status bits for jack_status_t return pointer:

JackNameNotUnique means that the client name was not unique. With JackUseExactName, this is fatal. Otherwise, the name was modified by appending a dash and a two-digit number in the range "-01" to "-99". The jack_get_client_name() function returns the exact string used. If the specified client_name plus these extra characters would be too long, the open fails instead.

JackServerStarted means that the JACK server was started as a result of this operation. Otherwise, it was running already. In either case the caller is now connected to jackd, so there is no race condition. When the server shuts down, the client will find out.

JackOpenOptions:

```
JackSessionID | JackServerName | JackNoStartServer | JackUseExactName
Only the first is used at present.
```

clientname

Provides the name of the client, used in the call to jack_client_open(). By default, this name is the macro SEQ64_PACKAGE (i.e. "sequencer64"). The name scope is local to each server. Unless forbidden by the JackUseExactName option, the server will modify this name to create a unique variant, if needed.

Returns

Returns a pointer to the JACK client if JACK has opened the client connection successfully. Otherwise, a null pointer is returned.

12.22.2.44 get_jack_client_info()

```
void seq64::jack_assistant::get_jack_client_info ( ) [private]
```

Sets m_jack_client_name and m_jack_client_info as side-effects.

12.22.2.45 show_statuses()

For reference, here are the enumeration values from /usr/include/jack/types.h:

```
        JackFailure
        = 0x01

        JackInvalidOption
        = 0x02

        JackNameNotUnique
        = 0x04

        JackServerStarted
        = 0x08

        JackServerFailed
        = 0x10

        JackServerError
        = 0x20

        JackNoSuchClient
        = 0x40

        JackLoadFailure
        = 0x80

        JackInitFailure
        = 0x200

        JackShmFailure
        = 0x200

        JackVersionError
        = 0x400

        JackBackendError
        = 0x800

        JackClientZombie
        = 0x1000
```

Parameters

bits The mask of the bits to be shown in the output.

12.22.2.46 show_position()

This function is meant for experimenting and learning.

The fields of this structure are as follows. Only the fields we care about are shown.

```
jack_nframes_t frame_rate: current frame rate (per second)
jack_nframes_t frame: frame number, always present
jack_position_bits_t valid: which other fields are valid
JackPositionBBT:
                     bar: current bar
beat: current beat-within-bar
tick: current file
   int32_t
    int32_t
   int32_t
double
                     tick:
bar_start_tick
                                      current tick-within-beat
                     beats_per_bar: time signature "numerator"
    float
                     beat_type: time signature "denominator" ticks_per_beat
    float
    double
                     beats_per_minute
    double
JackBBTFrameOffset:
    jack_nframes_t
                      bbt_offset;
                                     frame offset for the BBT fields
Only the most "important" and time-varying fields are shown. The format
output is brief and inscrutable unless you read this format example:
    nnnnn frame B:B:T N/D TPB BPM BBT
                     1 1 1
                     | | | | ------ bbt_offset (frame), even if invalid
                             -----beats_per_minute
                     1 1
                          ----- ticks_per_beat (PPQN * 10?)
                | | -----beat_type (denominator)
                     -----beats_per_bar (numerator)
                  ----- bar : beat : tick
             ----- frame (number)
                 ----- the "valid" bits
The "valid" field is shown as bits in the same bit order as shown here, but
represented as a five-character string, "nnnnn", n = 0 or 1:
    JackVideoFrameOffset = 0x100
    JackAudioVideoRatio = 0x080
    JackBBTFrameOffset = 0x040
    JackPositionTimecode = 0x020
    JackPositionBBT
                        = 0x010
We care most about nnnnn = "00101" in our experiments (the most common
output will be "00001"). And we don't worry about non-integer
measurements... we truncate them to integers. Change the output format if
you want to play with non-Western timings.
```

pos The JACK position structure to dump.

12.22.2.47 sync()

Sequencer64 is not a slow-sync client (and Stazed support doesn't use it), so that callback is not really needed, but we probably need this sub-function here to start out with the right values for interacting with JACK.

Note the call to jack_transport_query(). This call is *not* is seq24, but seems to be needed in sequencer64 because we put m_jack_pos in the initializer list, which sets all its fields to 0. Seq24 accesses m_jack_pos before it ever gets set, but its fields have values. These values are bogus, but are consistent from run to run on my computer, and allow seq24 to follow another JACK Master, on some computers. It explains why people had different experiences with JACK sync.

If we explicity call jack_transport_query() here, without changing the *state* parameter, then sequencer64 also can follow another JACK Master. (CURRENTLY BUGGY!)

Note that we should consider massaging the following jack_position_t members to set them to 0 (or 0.0) if less than 1.0 or 0.5:

```
- bar_start_tick
- ticks_per_beat
- beats_per_minute
- frame_time
- next_time
- audio_frames_per_video_frame
```

Also, why does bbt offset start at 2128362496?

Parameters

```
state The JACK transport state to be set.
```

12.22.2.48 set_position()

We might be able to use it in other functions.

Computing the BBT information from the frame number is relatively simple here, but would become complex if we supported tempo or time signature changes at specific locations in the transport timeline.

```
ticks * 10 = jack ticks;
jack ticks / ticks per beat = num beats;
num beats / beats per minute = num minutes
num minutes * 60 = num seconds
num secords * frame_rate = frame
```

Parameters

currenttick Provides the current position to be set.

12.22.3 Friends And Related Function Documentation

12.22.3.1 jack process_callback

12.22.3.2 jack_shutdown_callback

```
void jack_shutdown_callback ( \mbox{void} \ * \ arg \ ) \ \ [\mbox{friend}]
```

Parameters

arg Points to the jack_assistant in charge of JACK support for the perform object.

12.22.3.3 jack_sync_callback

```
int jack_sync_callback (
          jack_transport_state_t state,
          jack_position_t * pos,
          void * arg ) [friend]
```

This JACK synchronization callback informs the specified perform object of the current state and parameters of JACK.

The transport state will be:

- JackTransportStopped when a new position is requested.
- JackTransportStarting when the transport is waiting to start.
- JackTransportRolling when the timeout has expired, and the position is now a moving target.

This is the slow-sync callback, which the stazed code replaces with jack_process_callback().

Parameters

state	The JACK Transport state.
pos	The JACK position value.
arg	The pointer to the jack_assistant object. Currently not checked for nullity, nor dynamic-casted.

Returns

Returns 1 if the function works, and 0 if something was wrong.

12.22.3.4 jack_timebase_callback

```
void jack_timebase_callback (
          jack_transport_state_t state,
          jack_nframes_t nframes,
          jack_position_t * pos,
          int new_pos,
          void * arg ) [friend]
```

The original version of the function worked properly with Hydrogen, but not with Klick. The new code seems to work with both. More testing and clarification is needed. This new code was "discovered" in the source-code for the "SooperLooper" project:

http://essej.net/sooperlooper/

The first difference with the new code is that it handles the case where the JACK position is moved (new_pos == true). If this is true, and the JackPositionBBT bit is off in pos->valid, then the new BBT value is set.

The seconds set of differences are in the "else" clause. In the new code, it is very simple: calculate the new tick value, back it off by the number of ticks in a beat, and perhaps go to the first beat of the next bar.

In the old code (complex!), the simple BBT adjustment is always made. This changes (perhaps) the beats_per_bar, beat_type, etc. We need to make these settings use the actual global values for beats set for Sequencer64. Then, if transitioning from JackTransportStarting to JackTransportRolling (instead of checking new_pos!), the BBT values (bar, beat, and tick) are finally adjusted. Here are the steps, with old and new steps noted:

- -# Calculate the "delta" ticks based on the current frame, the ticks_per_beat, the beats_per_minute, and the frame_rate. The old code saves this in a local, the new code assigns it to pos->tick.
- -# Old code: save this delta as a positive value.
- -# Figure out the settings and modify bar, beat, tick, and bar_start_tick. The old and new code seem to have the same intent, but it seems like the new code is faster and also correct.
 - Old code: Calculations are made by division and mod operations.
 - New code: Calculations are made by increments and decrements in a while loop.

Stazed:

The call to jack_timebase_callback() to supply JACK with BBT, etc. would occasionally fail when the pos information had zero or some garbage in the pos.frame_rate variable. This would occur when there was a rapid change of frame position by another client... i.e. qjackctl. From the JACK API:

pos address of the position structure for the next cycle; pos->frame will be its frame number. If new_pos is FALSE, this structure contains extended position information from the current cycle. If TRUE, it contains whatever was set by the requester. The timebase_callback's task is to update the extended information here."

The "If TRUE" line seems to be the issue. It seems that qjackctl does not always set pos.frame_rate so we get garbage and some strange BBT calculations that display in qjackctl. So we need to set it here and just use m_jack_frame_rate for calculations instead of pos.frame_rate.

Parameters

state	Indicates the current state of JACK transport.
nframes	The number of JACK frames in the current time period.
pos	Provides the position structure to be filled in, the address of the position structure for the next cycle; pos->frame will be its frame number. If new_pos is FALSE, this structure contains extended position information from the current cycle. If TRUE, it contains whatever was set by the requester. The timebase_callback's task is to update the extended information here.
new_pos	TRUE (non-zero) for a newly requested pos, or for the first cycle after the timebase_callback is defined. This is usually 0 in Sequencer64 at present, and 1 if one, say, presses "rewind" in qjackctl.
arg	Provides the jack_assistant pointer, currently unchecked for nullity.

12.22.3.5 jack_session_callback

```
void jack_session_callback (
          jack_session_event_t * ev,
          void * arg ) [friend]
```

Glib is then used to connect in perform::jack_session_event(). However, the perform object's GUI-support interface is used instead of the following, so that the libseq64 library can be independent of a specific GUI framework:

```
Glib::signal_idle().
    connect(sigc::mem_fun(*jack, &jack_assistant::session_event));
```

Parameters

ev	The JACK event to be set.
arg	The pointer to the jack_assistant object. Currently not checked for nullity.

12.22.4 Field Documentation

12.22.4.1 sm_status_pairs

```
jack_status_pair_t seq64::jack_assistant::sm_status_pairs [static], [private]
```

Provides a list of JACK status bits, and a brief string to explain the status bit.

Terminated by a 0 value and an empty string.

```
12.22.4.2 m_jack_parent
```

```
perform& seq64::jack_assistant::m_jack_parent [private]
```

12.22.4.3 m_jack_client

```
jack_client_t* seq64::jack_assistant::m_jack_client [private]
```

12.22.4.4 m_jack_client_name

```
std::string seq64::jack_assistant::m_jack_client_name [private]
```

We might show this in the user-interface at some point.

12.22.4.5 m_jack_client_uuid

```
std::string seq64::jack_assistant::m_jack_client_uuid [private]
```

We might show this in the user-interface at some point.

```
12.22.4.6 m_jack_frame_current
```

```
jack_nframes_t seq64::jack_assistant::m_jack_frame_current [private]
```

12.22.4.7 m_jack_frame_last

```
jack_nframes_t seq64::jack_assistant::m_jack_frame_last [private]
```

Also used in incrementing m_jack_tick.

12.22.4.8 m_jack_pos

```
jack_position_t seq64::jack_assistant::m_jack_pos [private]
```

This structure is filled via a call to jack_transport_query(). It holds, among other items, the frame rate (often 48000), the ticks/beat, and the beats/minute.

12.22.4.9 m_jack_transport_state

```
jack_transport_state_t seq64::jack_assistant::m_jack_transport_state [private]
```

Common values are JackTransportStopped, JackTransportRolling, and JackTransportLooping.

12.22.4.10 m_jack_transport_state_last

```
jack_transport_state_t seq64::jack_assistant::m_jack_transport_state_last [private]
```

12.22.4.11 m_jack_tick

```
double seq64::jack_assistant::m_jack_tick [private]
```

12.22.4.12 m_jsession_ev

```
jack_session_event_t* seq64::jack_assistant::m_jsession_ev [private]
```

Used in the session_event() function.

12.22.4.13 m_jack_running

```
bool seq64::jack_assistant::m_jack_running [private]
```

12.22.4.14 m_jack_master

```
bool seq64::jack_assistant::m_jack_master [private]
```

```
12.22.4.15 m_jack_frame_rate
```

```
jack_nframes_t seq64::jack_assistant::m_jack_frame_rate [private]
```

Just in case. QJackCtl does not always set pos.frame_rate, so we get garbage and some strange BBT calculations displayed in qjackctl.

12.22.4.16 m_toggle_jack

```
bool seq64::jack_assistant::m_toggle_jack [private]
```

12.22.4.17 m_jack_stop_tick

```
midipulse seq64::jack_assistant::m_jack_stop_tick [private]
```

Repositions the transport marker.

12.22.4.18 m_follow_transport

```
bool seq64::jack_assistant::m_follow_transport [private]
```

12.22.4.19 m_ppqn

```
int seq64::jack_assistant::m_ppqn [private]
```

It is used for calculating ticks/beat (pulses/beat) and for setting the tick position.

12.22.4.20 m_beats_per_measure

```
int seq64::jack_assistant::m_beats_per_measure [private]
```

12.22.4.21 m_beat_width

```
int seq64::jack_assistant::m_beat_width [private]
```

12.22.4.22 m_beats_per_minute

```
int seq64::jack_assistant::m_beats_per_minute [private]
```

12.23 seq64::jack_scratchpad Class Reference

Provide a temporary structure for passing data and results between a perform and jack_assistant object.

Data Fields

· double js_current_tick

Holds current location.

double js_total_tick

Current location ignoring L/R.

· double is clock tick

Identical to js_total_tick.

bool js_jack_stopped

Flags perform::inner_stop().

bool js_dumping

Non-JACK playback in progress?

bool js_init_clock

We now have a good JACK lock.

bool js_looping

seqedit loop button is active.

bool js_playback_mode

Song mode (versus live mode).

· double js_ticks_converted

Keeps track of ...?

· double js_ticks_delta

Minor difference in tick.

· double js_ticks_converted_last

Keeps track of position?

long js_delta_tick_frac

More precision for seq24 0.9.3.

12.23.1 Detailed Description

The jack_assistant class already has access to the members of perform, but it needs access to and modification of "local" variables in perform::output_func(). This scratchpad is useful even if JACK support is not enabled.

12.23.2 Field Documentation

```
12.23.2.1 js_current_tick
```

```
double seq64::jack_scratchpad::js_current_tick
```

12.23.2.2 js_total_tick

```
double seq64::jack_scratchpad::js_total_tick
```

12.23.2.3 js_clock_tick

 $\verb|double seq64::jack_scratchpad::js_clock_tick|\\$

12.23.2.4 js_jack_stopped bool seq64::jack_scratchpad::js_jack_stopped 12.23.2.5 js_dumping bool seq64::jack_scratchpad::js_dumping 12.23.2.6 js_init_clock bool seq64::jack_scratchpad::js_init_clock 12.23.2.7 js_looping bool seq64::jack_scratchpad::js_looping 12.23.2.8 js_playback_mode bool seq64::jack_scratchpad::js_playback_mode 12.23.2.9 js_ticks_converted double seq64::jack_scratchpad::js_ticks_converted 12.23.2.10 js_ticks_delta double seq64::jack_scratchpad::js_ticks_delta 12.23.2.11 js_ticks_converted_last double seq64::jack_scratchpad::js_ticks_converted_last 12.23.2.12 js_delta_tick_frac

12.24 seq64::jack_status_pair_t Struct Reference

long seq64::jack_scratchpad::js_delta_tick_frac

Provides an internal type to make it easier to display a specific and accurate human-readable message when a JACK operation fails.

Data Fields

unsigned jf_bit

Holds one of the bit-values from jack_status_t, which is defined as an "enum JackStatus" type.

• std::string jf_meaning

Holds a textual description of the corresponding status bit.

12.24.1 Field Documentation

```
12.24.1.1 jf_bit
unsigned seq64::jack_status_pair_t::jf_bit
12.24.1.2 jf_meaning
```

12.25 seq64::keybindentry Class Reference

std::string seq64::jack_status_pair_t::jf_meaning

Class for management of application key-bindings.

Inherits Entry.

Public Member Functions

• keybindentry (type t, unsigned int *location_to_write=nullptr, perform *p=nullptr, long s=0)

This constructor initializes the member with values dependent on the value type provided in the first parameter.

• void set (unsigned int val)

Gets the key name from the integer value; if there is one, then it is printed into a temporary buffer, otherwise the value is printed into that buffer as is.

virtual bool on_key_press_event (GdkEventKey *event)

Handles a key press by calling set() with the event's key value.

Private Types

```
enum type {
location,
events,
groups }
```

Provides the type of keybindings that can be made.

Private Attributes

unsigned int * m_key

Points to the value of the key that is part of this key-binding.

• type m_type

Stores the type of key-binding.

• perform * m_perf

Stores an optional pointer to a perform object.

• long m_slot

Provides an index into a set of group-keys or event-keys.

Friends

• class options

12.25.1 Member Enumeration Documentation

```
12.25.1.1 type
```

```
enum seq64::keybindentry::type [private]
```

Enumerator

location	Used for handling a keystroke made while a keyboard-options field is active, for selecting a key via the keyboard, and binding to pattern/sequence boxes, we think. It is used in the options class to associate a key with the binding.
events	Used for binding to events.
groups	Used for binding to groups.

12.25.2 Constructor & Destructor Documentation

12.25.2.1 keybindentry()

Usage In options, a pointer to a new key-binding entry is managed by calling keybindentry (keybindentry ::location, &perf→keyname).

Parameters

t	Provides the type of key-binding: location, events, or groups.
location_to_write	The location that holds the value of the key associated with the key-binding. The default value of this parameter is the null pointer.
p	Points to the performance object used with this key-binding. The default value of this parameter is the null pointer.
S	Provides the slot value for this key-binding. The default value of this parameter is zero Doxygen

12.25.3 Member Function Documentation

Then we call set_text(buf). The set_width_char() function is then called.

```
12.25.3.2 on_key_press_event()
```

This value is used to set the event or key depending on the value of m_type.

Parameters

Returns

Returns the result of the call to Entry::on_key_press_event().

12.25.4 Friends And Related Function Documentation

12.25.4.1 options

```
friend class options [friend]
```

12.25.5 Field Documentation

```
12.25.5.1 m_key
```

```
unsigned int* seq64::keybindentry::m_key [private]
```

Not yet sure by the address of this key value is needed. It can be a null pointer, as well.

```
12.25.5.2 m_type
```

```
type seq64::keybindentry::m_type [private]
```


12.25.5.3 m_perf

```
perform* seq64::keybindentry::m_perf [private]
```



This class supports the performance mode.

Inheritance diagram for seq64::keys_perform:



Public Member Functions

• keys_perform ()

This construction initializes a vast number of member variables, some of them public!

virtual ~keys_perform ()

The destructor sets some running flags to false, signals this condition, then joins the input and output threads if the were launched.

void set_keys (const keys_perform_transfer &kpt)

Copies fields from the transfer structure in this object.

void get_keys (keys_perform_transfer &kpt)

Copies fields from this object into the transfer structure.

unsigned int bpm_up () const

'Getter' function for member m_key_bpm_up

void bpm_up (unsigned int x)

'Setter' function for member m_key_bpm_up

unsigned int bpm_dn () const

'Getter' function for member m_key_bpm_dn

void bpm dn (unsigned int x)

'Setter' function for member m_key_bpm_dn

unsigned int replace () const

'Getter' function for member m_key_replace

void replace (unsigned int x)

'Setter' function for member m_key_replace

• unsigned int queue () const

'Getter' function for member m_key_queue

void queue (unsigned int x)

'Setter' function for member m_key_queue

• unsigned int keep_queue () const

'Getter' function for member m_key_keep_queue

• void keep_queue (unsigned int x)

'Setter' function for member m_key_keep_queue

unsigned int snapshot_1 () const

'Getter' function for member m_key_snapshot_1

void snapshot_1 (unsigned int x)

'Setter' function for member m_key_snapshot_1

• unsigned int snapshot_2 () const

'Getter' function for member m_key_snapshot_2

void snapshot_2 (unsigned int x)

'Setter' function for member m_key_snapshot_2

• unsigned int screenset_up () const

'Getter' function for member m_key_screenset_up

void screenset_up (unsigned int x)

'Setter' function for member m_key_screenset_up

unsigned int screenset_dn () const

'Getter' function for member m_key_screenset_dn

void screenset_dn (unsigned int x)

'Setter' function for member m_key_screenset_dn

• unsigned int set_playing_screenset () const

'Getter' function for member m_key_playing_screenset

void set_playing_screenset (unsigned int x)

 ${\it 'Setter' function for member m_key_playing_screenset}$

• unsigned int group_on () const

'Getter' function for member m_key_group_on

void group_on (unsigned int x)

'Setter' function for member m_key_group_on

• unsigned int group off () const

'Getter' function for member m_key_group_off

void group_off (unsigned int x)

'Setter' function for member m_key_group_off

· unsigned int group_learn () const

'Getter' function for member m_key_group_learn

void group learn (unsigned int x)

'Setter' function for member m_key_group_learn

• unsigned int start () const

'Getter' function for member m_key_start

void start (unsigned int x)

'Setter' function for member m_key_start

• unsigned int pause () const

'Getter' function for member m_key_pause

void pause (unsigned int x)

'Setter' function for member m_key_pause

• unsigned int pattern_edit () const

'Getter' function for member m_key_pattern_edit

void pattern_edit (unsigned int x)

'Setter' function for member m_key_pattern_edit

• unsigned int event_edit () const

'Getter' function for member m_key_event_edit

void event_edit (unsigned int x)

'Setter' function for member m_key_event_edit

• unsigned int stop () const

'Getter' function for member m_key_stop

void stop (unsigned int x)

'Setter' function for member m key stop

- unsigned int song mode () const
- void song_mode (unsigned int key)
- unsigned int menu_mode () const
- void menu mode (unsigned int key)
- unsigned int follow_transport () const
- void follow_transport (unsigned int key)
- unsigned int fast_forward () const
- void fast_forward (unsigned int key)
- unsigned int rewind () const
- void rewind (unsigned int key)
- unsigned int pointer_position () const
- void pointer position (unsigned int key)
- unsigned int toggle_mutes () const
- void toggle_mutes (unsigned int key)
- unsigned int toggle_jack () const
- void toggle_jack (unsigned int key)
- unsigned int tap_bpm () const
- void tap_bpm (unsigned int key)
- bool show_ui_sequence_key () const

'Getter' function for member m_key_show_ui_sequency_key

void show ui sequence key (bool flag)

'Setter' function for member m_key_show_ui_sequency_key

bool show_ui_sequence_number () const

'Getter' function for member m_key_show_ui_sequence_number

void show_ui_sequence_number (bool flag)

'Setter' function for member m_key_show_ui_sequence_key

• SlotMap & get_key_events ()

'Getter' function for member m_key_events

SlotMap & get_key_groups ()

'Getter' function for member m_key_groups

RevSlotMap & get_key_events_rev ()

'Getter' function for member m_key_events_rev

RevSlotMap & get_key_groups_rev ()

'Getter' function for member m_key_groups_rev

unsigned int lookup keyevent key (long segnum)

'Getter' function for member m_key_events_rev[seqnum];

long lookup_keyevent_seq (unsigned int keycode)

'Getter' function for member m key events rev[keycode];

unsigned int lookup_keygroup_key (long groupnum)

'Getter' function for member m_key_events_rev[groupnum];

long lookup_keygroup_group (unsigned int keycode)

'Getter' function for member m_key_events_rev[keycode];

· virtual std::string key_name (unsigned int key) const

Obtains the name of the key.

virtual void set_all_key_events ()

Provides base class functionality.

virtual void set all key groups ()

Provides base class functionality.

void set key event (unsigned int keycode, long sequence slot)

At construction time, this function sets up one keycode and one event slot.

void set_key_group (unsigned int keycode, long group_slot)

At construction time, this function sets up one keycode and one group slot.

Protected Types

typedef std::map< unsigned int, long > SlotMap

This typedef defines a map in which the key is the keycode, that is, the integer value of a keystroke, and the value is the pattern/sequence number or slot.

typedef std::map< long, unsigned int > RevSlotMap

This typedef is like SlotMap, but used for lookup in the other direction.

Protected Member Functions

unsigned int * at_bpm_up ()

The following are tricky ways to get at address of the key and group operation values so that we don't directly expose the members to manipulation.

• unsigned int * at bpm dn ()

'Getter' function for member m_key_bpm_dn

unsigned int * at_replace ()

'Getter' function for member m_key_replace

• unsigned int * at_queue ()

'Getter' function for member m_key_queue

unsigned int * at_keep_queue ()

'Getter' function for member m_key_keep_queue

unsigned int * at snapshot 1 ()

'Getter' function for member m_key_snapshot_1

unsigned int * at_snapshot_2 ()

```
'Getter' function for member m_key_snapshot_2
unsigned int * at_screenset_up ()
      'Getter' function for member m_key_screenset_up
unsigned int * at_screenset_dn ()
      'Getter' function for member m_key_screenset_dn

    unsigned int * at_set_playing_screenset ()

      'Getter' function for member m_key_playing_screenset
unsigned int * at_group_on ()
      'Getter' function for member m_key_group_on
unsigned int * at_group_off ()
      'Getter' function for member m_key_group_off

    unsigned int * at group learn ()

      'Getter' function for member m_key_group_learn
• unsigned int * at start ()
      'Getter' function for member m key start
unsigned int * at_pause ()
      'Getter' function for member m_key_pause
unsigned int * at_song_mode ()
      'Getter' function for member m_key_song_mode
unsigned int * at_toggle_jack ()
      'Getter' function for member m_key_toggle_jack

    unsigned int * at_menu_mode ()

      'Getter' function for member m_key_menu_mode

    unsigned int * at follow transport ()

      'Getter' function for member m_key_follow_transport
unsigned int * at_fast_forward ()
      'Getter' function for member m_key_fast_forward
unsigned int * at_rewind ()
      'Getter' function for member m_key_rewind
unsigned int * at_pointer_position ()
      'Getter' function for member m_key_pointer_position
• unsigned int * at_toggle_mutes ()
      'Getter' function for member m_key_toggle_mutes
unsigned int * at_tap_bpm ()
      'Getter' function for member m_key_tap_bpm
unsigned int * at_pattern_edit ()
      'Getter' function for member m key pattern edit
unsigned int * at_event_edit ()
      'Getter' function for member m key event edit
unsigned int * at_stop ()
      'Getter' function for member m_key_stop
bool * at_show_ui_sequence_key ()
      'Getter' function for member m_key_show_ui_sequence_key
bool * at_show_ui_sequence_number ()
      'Getter' function for member m_key_show_ui_sequence_number
```

Private Attributes

bool m_key_show_ui_sequence_key

If set, shows the shortcut-keys on each filled pattern slot in the main window.

• bool m_key_show_ui_sequence_number

If set, shows the sequence number on each filled pattern and empty pattern slot in the main window.

• SlotMap m_key_events

Holds the mapping of keys to the pattern slots.

SlotMap m_key_groups

Holds the mapping of keys to the mute groups.

RevSlotMap m_key_events_rev

Holds the reverse mapping of the pattern slots to the keys.

RevSlotMap m_key_groups_rev

Holds the reverse mapping of the mute groups to the keys.

unsigned int m_key_bpm_up

Provides key assignments for some key sequencer features.

• unsigned int m_key_bpm_dn

BPM down, semicolon.

• unsigned int m_key_replace

Replace, Ctrl-L.

• unsigned int m_key_queue

Queue, Ctrl-R.

• unsigned int m_key_keep_queue

Keep queue, backslash.

• unsigned int m_key_snapshot_1

Snapshot 1, Alt-L.

• unsigned int m_key_snapshot_2

Snapshot 1, Alt-R.

unsigned int m_key_screenset_up

Set up, Right-].

· unsigned int m key screenset dn

Set down, Left-[.

• unsigned int m_key_set_playing_screenset

Set set, Home key.

unsigned int m_key_group_on

Group on, igrave key.

• unsigned int m_key_group_off

Group off, apostrophe!

• unsigned int m_key_group_learn

Group learn, Insert.

• unsigned int m_key_start

Start play, Space key.

unsigned int m_key_pause

Pause play, Period.

• unsigned int m_key_song_mode

Song versus Live mode.

unsigned int m_key_toggle_jack

Toggle JACK connect.

· unsigned int m key menu mode

Menu enabled/disabled.

• unsigned int m_key_follow_transport

Toggle following JACK.

• unsigned int m_key_rewind

Start rewind.

• unsigned int m_key_fast_forward

Start fast-forward.

• unsigned int m_key_pointer_position

Set progress to mouse.

unsigned int m_key_toggle_mutes

Toggle all patterns.

unsigned int m_key_tap_bpm

To tap out the BPM.

• unsigned int m_key_pattern_edit

Show pattern editor.

• unsigned int m_key_event_edit

Show event editor.

• unsigned int m_key_stop

Stop play, Escape.

Friends

- · class options
- · class perform
- · class optionsfile

12.26.1 Detailed Description

It provides a way a mapping keystrokes to sequencer actions and song settings.

12.26.2 Member Typedef Documentation

12.26.2.1 SlotMap

```
typedef std::map<unsigned int, long> seq64::keys_perform::SlotMap [protected]
```

12.26.2.2 RevSlotMap

```
{\tt typedef std::map<long, unsigned int> seq64::keys\_perform::RevSlotMap} \quad [protected]
```

12.26.3 Constructor & Destructor Documentation

12.26.3.1 keys_perform()

```
seq64::keys\_perform::keys\_perform ( )
```

```
12.26.3.2 \simkeys_perform()
```

```
seq64::keys_perform::~keys_perform ( ) [virtual]
```

Finally, any active patterns/sequences are deleted.

12.26.4 Member Function Documentation

This structure holds all of the key settings from the File / Options / Keyboard tab dialog.

Parameters

kpt

The structure that holds the values of the keys to be used for various purposes in controlling a performance live.

12.26.4.2 get_keys()

Parameters

kpt

The structure that holds the values of the keys to be used for various purposes in controlling a performance live.

```
12.26.4.3 bpm_up() [1/2]
```

```
unsigned int seq64::keys_perform::bpm_up ( ) const [inline]
```

12.26.4.4 bpm_up() [2/2]

Parameters

x The key value to assign to the operation.

```
12.26.4.5 bpm_dn() [1/2]
unsigned int seq64::keys_perform::bpm_dn ( ) const [inline]
12.26.4.6 bpm_dn() [2/2]
void seq64::keys_perform::bpm_dn (
            unsigned int x ) [inline]
Parameters
     The key value to assign to the operation.
12.26.4.7 replace() [1/2]
unsigned int seq64::keys_perform::replace ( ) const [inline]
12.26.4.8 replace() [2/2]
void seq64::keys_perform::replace (
             unsigned int x ) [inline]
Parameters
     The key value to assign to the operation.
12.26.4.9 queue() [1/2]
unsigned int seq64::keys_perform::queue ( ) const [inline]
12.26.4.10 queue() [2/2]
void seq64::keys_perform::queue (
             unsigned int x ) [inline]
Parameters
     The key value to assign to the operation.
12.26.4.11 keep_queue() [1/2]
unsigned int seq64::keys_perform::keep_queue ( ) const [inline]
```

```
12.26.4.12 keep_queue() [2/2]
void seq64::keys_perform::keep_queue (
             unsigned int x ) [inline]
Parameters
     The key value to assign to the operation.
12.26.4.13 snapshot_1() [1/2]
unsigned int seq64::keys_perform::snapshot_1 ( ) const [inline]
12.26.4.14 snapshot_1() [2/2]
void seq64::keys_perform::snapshot_1 (
             unsigned int x ) [inline]
Parameters
     The key value to assign to the operation.
12.26.4.15 snapshot_2() [1/2]
unsigned int seq64::keys_perform::snapshot_2 ( ) const [inline]
12.26.4.16 snapshot_2() [2/2]
void seq64::keys_perform::snapshot_2 (
             unsigned int x ) [inline]
Parameters
     The key value to assign to the operation.
12.26.4.17 screenset_up() [1/2]
unsigned int seq64::keys_perform::screenset_up ( ) const [inline]
12.26.4.18 screenset_up() [2/2]
void seq64::keys_perform::screenset_up (
```

unsigned int x) [inline]

Parameters

```
x The key value to assign to the operation.
```

Parameters

x The key value to assign to the operation.

Parameters

x The key value to assign to the operation.

Parameters

The key value to assign to the operation.

```
12.26.4.25 group_off() [1/2]
unsigned int seq64::keys_perform::group_off ( ) const [inline]
12.26.4.26 group_off() [2/2]
void seq64::keys_perform::group_off (
            unsigned int x ) [inline]
Parameters
     The key value to assign to the operation.
12.26.4.27 group_learn() [1/2]
unsigned int seq64::keys_perform::group_learn ( ) const [inline]
12.26.4.28 group_learn() [2/2]
void seq64::keys_perform::group_learn (
             unsigned int x ) [inline]
Parameters
     The key value to assign to the operation.
12.26.4.29 start() [1/2]
unsigned int seq64::keys_perform::start ( ) const [inline]
12.26.4.30 start() [2/2]
void seq64::keys_perform::start (
             unsigned int x ) [inline]
Parameters
     The key value to assign to the operation.
12.26.4.31 pause() [1/2]
unsigned int seq64::keys_perform::pause ( ) const [inline]
```

```
12.26.4.32 pause() [2/2]
void seq64::keys_perform::pause (
             unsigned int x ) [inline]
Parameters
     The key value to assign to the operation.
12.26.4.33 pattern_edit() [1/2]
unsigned int seq64::keys_perform::pattern_edit ( ) const [inline]
12.26.4.34 pattern_edit() [2/2]
void seq64::keys_perform::pattern_edit (
             unsigned int x ) [inline]
Parameters
     The key value to assign to the operation.
12.26.4.35 event_edit() [1/2]
unsigned int seq64::keys_perform::event_edit ( ) const [inline]
12.26.4.36 event_edit() [2/2]
void seq64::keys_perform::event_edit (
             unsigned int x ) [inline]
Parameters
     The key value to assign to the operation.
12.26.4.37 stop() [1/2]
unsigned int seq64::keys_perform::stop ( ) const [inline]
12.26.4.38 stop() [2/2]
void seq64::keys_perform::stop (
              unsigned int x ) [inline]
```

Parameters

The key value to assign to the operation.

```
12.26.4.39 song_mode() [1/2]
unsigned int seq64::keys_perform::song_mode ( ) const [inline]
12.26.4.40 song_mode() [2/2]
void seq64::keys_perform::song_mode (
             unsigned int key ) [inline]
12.26.4.41 menu_mode() [1/2]
unsigned int seq64::keys_perform::menu_mode ( ) const [inline]
12.26.4.42 menu_mode() [2/2]
void seq64::keys_perform::menu_mode (
             unsigned int key ) [inline]
12.26.4.43 follow_transport() [1/2]
unsigned int seq64::keys_perform::follow_transport ( ) const [inline]
12.26.4.44 follow_transport() [2/2]
void seq64::keys_perform::follow_transport (
             unsigned int key ) [inline]
12.26.4.45 fast_forward() [1/2]
unsigned int seq64::keys_perform::fast_forward ( ) const [inline]
12.26.4.46 fast_forward() [2/2]
void seq64::keys_perform::fast_forward (
             unsigned int key ) [inline]
```

```
12.26.4.47 rewind() [1/2]
unsigned int seq64::keys_perform::rewind ( ) const [inline]
12.26.4.48 rewind() [2/2]
void seq64::keys_perform::rewind (
             unsigned int key ) [inline]
12.26.4.49 pointer_position() [1/2]
unsigned int seq64::keys_perform::pointer_position ( ) const [inline]
12.26.4.50 pointer_position() [2/2]
void seq64::keys_perform::pointer_position (
             unsigned int key ) [inline]
12.26.4.51 toggle_mutes() [1/2]
unsigned int seq64::keys_perform::toggle_mutes ( ) const [inline]
12.26.4.52 toggle_mutes() [2/2]
void seq64::keys_perform::toggle_mutes (
             unsigned int key ) [inline]
12.26.4.53 toggle_jack() [1/2]
unsigned int seq64::keys_perform::toggle_jack ( ) const [inline]
12.26.4.54 toggle_jack() [2/2]
void seq64::keys_perform::toggle_jack (
             unsigned int key ) [inline]
12.26.4.55 tap_bpm() [1/2]
unsigned int seq64::keys_perform::tap_bpm ( ) const [inline]
```

```
12.26.4.56 tap_bpm() [2/2]
void seq64::keys_perform::tap_bpm (
             unsigned int key ) [inline]
12.26.4.57 show_ui_sequence_key() [1/2]
bool seq64::keys_perform::show_ui_sequence_key ( ) const [inline]
Used in mainwid, options, optionsfile, userfile, and perform.
12.26.4.58 show_ui_sequence_key() [2/2]
void seq64::keys_perform::show_ui_sequence_key (
             bool flag ) [inline]
Parameters
 flag
       The flag for showing the sequence key characters in each pattern slot.
12.26.4.59 show_ui_sequence_number() [1/2]
bool seq64::keys_perform::show_ui_sequence_number ( ) const [inline]
Used in mainwid, options, optionsfile, userfile, and perform.
12.26.4.60 show_ui_sequence_number() [2/2]
void seq64::keys_perform::show_ui_sequence_number (
             bool flag ) [inline]
Parameters
 flaa
       The flag for showing the sequence number in each pattern slot.
12.26.4.61 get_key_events()
SlotMap& seq64::keys_perform::get_key_events ( ) [inline]
12.26.4.62 get_key_groups()
```

SlotMap& seq64::keys_perform::get_key_groups () [inline]

12.26.4.63 get_key_events_rev()

```
RevSlotMap& seq64::keys_perform::get_key_events_rev ( ) [inline]
```

12.26.4.64 get_key_groups_rev()

```
RevSlotMap& seq64::keys_perform::get_key_groups_rev ( ) [inline]
```

12.26.4.65 lookup_keyevent_key()

Parameters

seqnum

Provides the sequence number to look up in the reverse key map for patterns/sequences. If the count for this value is 0, then a question mark character is returned. Not checked for maximum!

12.26.4.66 lookup_keyevent_seq()

Parameters

keycode

Provides the keycode to look up in the (forward) key map for patterns/sequences. If the count for this value is 0, then a 0 is returned.

12.26.4.67 lookup_keygroup_key()

Parameters

groupnum

Provides the group number to look up in the reverse key map for groups. If the count for this value is 0, then a question mark character is returned.

12.26.4.68 lookup_keygroup_group()

Parameters

keycode	Provides the sequence number to look up in the reverse key map for groups. If the count for this
	value is 0, then a 0 is returned.

12.26.4.69 key_name()

In gtkmm, this is done via the gdk_keyval_name() function. Here, in the base class, we just provide an easy-to-create string.

Parameters

key Provides the numeric value of the keystroke.

Returns

Returns the name of the key, in the format "Key 0xkkkk".

Reimplemented in seq64::keys_perform_gtk2.

```
12.26.4.70 set_all_key_events()
```

```
virtual void seq64::keys_perform::set_all_key_events ( ) [inline], [virtual]
```

Must be called by the derived-class's override of this function.

Reimplemented in seq64::keys_perform_gtk2.

```
12.26.4.71 set_all_key_groups()
```

```
virtual void seq64::keys_perform::set_all_key_groups ( ) [inline], [virtual]
```

Must be called by the derived-class's override of this function.

Reimplemented in seq64::keys_perform_gtk2.

12.26.4.72 set_key_event()

```
void seq64::keys_perform::set_key_event (
          unsigned int keycode,
          long sequence_slot )
```

It is called 32 times, corresponding the pattern/sequence slots in the Patterns window.

Parameters

keycode	The key to be assigned.
sequence_slot	The perform event slot into which the keycode will be assigned.

12.26.4.73 set_key_group()

```
void seq64::keys_perform::set_key_group (
          unsigned int keycode,
          long group_slot )
```

It is called 32 times, corresponding the pattern/sequence slots in the Patterns window.

Parameters

keycode	The key to be assigned.
group_slot	The perform group slot into which the keycode will be assigned.

12.26.4.74 at_bpm_up()

```
unsigned int* seq64::keys_perform::at_bpm_up ( ) [inline], [protected]
```

They are used in the options module, and, for brevity, are accessed using the PREFKEY_ADDR() macro. 'Getter' function for member $m_{key_bpm_up}$

Address getter for the bpm_up operation.

```
12.26.4.75 at_bpm_dn()
```

```
unsigned int* seq64::keys_perform::at_bpm_dn ( ) [inline], [protected]
```

Address getter for the bpm_dn operation.

12.26.4.76 at_replace()

```
unsigned int* seq64::keys_perform::at_replace ( ) [inline], [protected]
```

Address getter for the replace operation.

```
12.26.4.77 at_queue()
```

```
unsigned int* seq64::keys_perform::at_queue ( ) [inline], [protected]
```

Address getter for the queue operation.

```
12.26.4.78 at_keep_queue()
unsigned int* seq64::keys_perform::at_keep_queue ( ) [inline], [protected]
Address getter for the keep_queue operation.
12.26.4.79 at_snapshot_1()
unsigned int* seq64::keys_perform::at_snapshot_1 ( ) [inline], [protected]
Address getter for the snapshot_1 operation.
12.26.4.80 at_snapshot_2()
unsigned int* seq64::keys_perform::at_snapshot_2 ( ) [inline], [protected]
Address getter for the snapshot 2 operation.
12.26.4.81 at_screenset_up()
unsigned int* seq64::keys_perform::at_screenset_up ( ) [inline], [protected]
Address getter for the screenset_up operation.
12.26.4.82 at_screenset_dn()
unsigned int* seq64::keys_perform::at_screenset_dn ( ) [inline], [protected]
Address getter for the screenset_dn operation.
12.26.4.83 at set playing screenset()
unsigned int* seq64::keys_perform::at_set_playing_screenset ( ) [inline], [protected]
Address getter for the set playing screenset operation.
12.26.4.84 at_group_on()
unsigned int* seq64::keys_perform::at_group_on ( ) [inline], [protected]
Address getter for the group_on operation.
12.26.4.85 at_group_off()
unsigned int* seq64::keys_perform::at_group_off ( ) [inline], [protected]
```

Address getter for the group_off operation.

```
12.26.4.86 at_group_learn()
unsigned int* seq64::keys_perform::at_group_learn ( ) [inline], [protected]
Address getter for the group_learn operation.
12.26.4.87 at_start()
unsigned int* seq64::keys_perform::at_start ( ) [inline], [protected]
Address getter for the start operation.
12.26.4.88 at_pause()
unsigned int* seq64::keys_perform::at_pause ( ) [inline], [protected]
Address getter for the pause operation.
12.26.4.89 at_song_mode()
unsigned int* seq64::keys_perform::at_song_mode ( ) [inline], [protected]
Address getter for the song-mode operation.
12.26.4.90 at_toggle_jack()
unsigned int* seq64::keys_perform::at_toggle_jack ( ) [inline], [protected]
Address getter for the toggle-jack operation.
12.26.4.91 at_menu_mode()
unsigned int* seq64::keys_perform::at_menu_mode ( ) [inline], [protected]
Address getter for the menu-mode operation.
12.26.4.92 at_follow_transport()
unsigned int* seq64::keys_perform::at_follow_transport ( ) [inline], [protected]
Address getter for the follow-transport operation.
12.26.4.93 at_fast_forward()
unsigned int* seq64::keys_perform::at_fast_forward ( ) [inline], [protected]
```

Address getter for the fast-forward operation.

```
12.26.4.94 at_rewind()
unsigned int* seq64::keys_perform::at_rewind ( ) [inline], [protected]
Address getter for the rewind operation.
12.26.4.95 at_pointer_position()
unsigned int* seq64::keys_perform::at_pointer_position ( ) [inline], [protected]
Address getter for the pointer operation.
12.26.4.96 at_toggle_mutes()
unsigned int* seq64::keys_perform::at_toggle_mutes ( ) [inline], [protected]
Address getter for the toggle-mutes operation.
12.26.4.97 at_tap_bpm()
unsigned int* seq64::keys_perform::at_tap_bpm () [inline], [protected]
Address getter for the tap_bpm operation.
12.26.4.98 at_pattern_edit()
unsigned int* seq64::keys_perform::at_pattern_edit ( ) [inline], [protected]
Address getter for the pattern-edit operation.
12.26.4.99 at_event_edit()
unsigned int* seq64::keys_perform::at_event_edit ( ) [inline], [protected]
Address getter for the event-edit operation.
12.26.4.100 at_stop()
unsigned int* seq64::keys_perform::at_stop ( ) [inline], [protected]
Address getter for the stop operation.
12.26.4.101 at_show_ui_sequence_key()
bool* seq64::keys_perform::at_show_ui_sequence_key ( ) [inline], [protected]
```

Address getter for the show_ui_sequence_key value.

```
12.26.4.102 at_show_ui_sequence_number()
bool* seq64::keys_perform::at_show_ui_sequence_number ( ) [inline], [protected]
Address getter for the show_ui_sequence_number value.
12.26.5 Friends And Related Function Documentation
12.26.5.1 options
friend class options [friend]
12.26.5.2 perform
friend class perform [friend]
12.26.5.3 optionsfile
friend class optionsfile [friend]
12.26.6 Field Documentation
12.26.6.1 m_key_show_ui_sequence_key
bool seq64::keys_perform::m_key_show_ui_sequence_key [private]
12.26.6.2 m_key_show_ui_sequence_number
bool seq64::keys_perform::m_key_show_ui_sequence_number [private]
Also shows the sequence number as part of the sequence name in the performance window (song editor). Always
disabled in legacy mode.
12.26.6.3 m_key_events
SlotMap seq64::keys_perform::m_key_events [private]
Do not access directly, use the set/lookup functions declared below.
12.26.6.4 m_key_groups
```

Do not access directly, use the set/lookup functions declared below.

SlotMap seq64::keys_perform::m_key_groups [private]

```
12.26.6.5 m_key_events_rev
```

```
RevSlotMap seq64::keys_perform::m_key_events_rev [private]
```

Do not access directly, use the set/lookup functions declared below.

```
12.26.6.6 m_key_groups_rev
```

```
RevSlotMap seq64::keys_perform::m_key_groups_rev [private]
```

Do not access directly, use the set/lookup functions declared below.

```
12.26.6.7 m_key_bpm_up
```

```
unsigned int seq64::keys_perform::m_key_bpm_up [private]
```

Used in mainwnd, options, optionsfile, perfedit, seqroll, userfile, and perform.

We could instead use the keys_perform_transfer structure instead of all these individual members.BPM up, apostrophe!!!

```
12.26.6.8 m_key_bpm_dn
```

```
unsigned int seq64::keys_perform::m_key_bpm_dn [private]
```

12.26.6.9 m_key_replace

```
unsigned int seq64::keys_perform::m_key_replace [private]
```

12.26.6.10 m_key_queue

```
unsigned int seq64::keys_perform::m_key_queue [private]
```

12.26.6.11 m_key_keep_queue

```
unsigned int seq64::keys_perform::m_key_keep_queue [private]
```

12.26.6.12 m_key_snapshot_1

```
unsigned int seq64::keys_perform::m_key_snapshot_1 [private]
```

12.26.6.13 m_key_snapshot_2

unsigned int seq64::keys_perform::m_key_snapshot_2 [private]


```
12.26.6.14 m_key_screenset_up
unsigned int seq64::keys_perform::m_key_screenset_up [private]
12.26.6.15 m_key_screenset_dn
unsigned int seq64::keys_perform::m_key_screenset_dn [private]
12.26.6.16 m_key_set_playing_screenset
unsigned int seq64::keys_perform::m_key_set_playing_screenset [private]
12.26.6.17 m_key_group_on
unsigned int seq64::keys_perform::m_key_group_on [private]
12.26.6.18 m_key_group_off
unsigned int seq64::keys_perform::m_key_group_off [private]
12.26.6.19 m_key_group_learn
unsigned int seq64::keys_perform::m_key_group_learn [private]
12.26.6.20 m_key_start
unsigned int seq64::keys_perform::m_key_start [private]
12.26.6.21 m_key_pause
unsigned int seq64::keys_perform::m_key_pause [private]
12.26.6.22 m_key_song_mode
unsigned int seq64::keys_perform::m_key_song_mode [private]
12.26.6.23 m_key_toggle_jack
unsigned int seq64::keys_perform::m_key_toggle_jack [private]
```

```
12.26.6.24 m_key_menu_mode
unsigned int seq64::keys_perform::m_key_menu_mode [private]
12.26.6.25 m_key_follow_transport
unsigned int seq64::keys_perform::m_key_follow_transport [private]
12.26.6.26 m_key_rewind
unsigned int seq64::keys_perform::m_key_rewind [private]
12.26.6.27 m_key_fast_forward
unsigned int seq64::keys_perform::m_key_fast_forward [private]
12.26.6.28 m_key_pointer_position
unsigned int seq64::keys_perform::m_key_pointer_position [private]
12.26.6.29 m_key_toggle_mutes
unsigned int seq64::keys_perform::m_key_toggle_mutes [private]
12.26.6.30 m_key_tap_bpm
unsigned int seq64::keys_perform::m_key_tap_bpm [private]
12.26.6.31 m_key_pattern_edit
unsigned int seq64::keys_perform::m_key_pattern_edit [private]
12.26.6.32 m_key_event_edit
unsigned int seq64::keys_perform::m_key_event_edit [private]
12.26.6.33 m_key_stop
unsigned int seq64::keys_perform::m_key_stop [private]
```

12.27 seq64::keys_perform_gtk2 Class Reference

This class supports the performance mode.

Inheritance diagram for seq64::keys_perform_gtk2:



Public Member Functions

• keys_perform_gtk2 ()

This construction initializes a vast number of member variables, some of them public!

virtual ~keys_perform_gtk2 ()

A rote virtual destructor.

- · virtual std::string key_name (unsigned int key) const
- virtual void set_all_key_events ()

Sets up the keys for arming/unmuting events in the Gtk-2 environment.

virtual void set_all_key_groups ()

Sets up the keys for group events in the Gtk-2 environment.

Additional Inherited Members

12.27.1 Detailed Description

It has way too many data members, many of the public. Might be ripe for refactoring.

12.27.2 Constructor & Destructor Documentation

```
12.27.2.1 keys_perform_gtk2()
```

```
seq64::keys_perform_gtk2::keys_perform_gtk2 ( )
```

12.27.2.2 \sim keys_perform_gtk2()

```
seq64::keys_perform_gtk2::~keys_perform_gtk2 ( ) [virtual]
```

No action.

12.27.3 Member Function Documentation

```
12.27.3.1 key_name()
```

Reimplemented from seq64::keys_perform.

```
12.27.3.2 set_all_key_events()
```

```
void seq64::keys_perform_gtk2::set_all_key_events ( ) [virtual]
```

The base-class function call makes sure the the related lists are cleared before rebuilding them here.

Reimplemented from seq64::keys_perform.

```
12.27.3.3 set_all_key_groups()
```

```
void seq64::keys_perform_gtk2::set_all_key_groups ( ) [virtual]
```

The base-class function call makes sure the the related lists are cleared before rebuilding them here.

Reimplemented from seq64::keys_perform.

12.28 seq64::keys_perform_transfer Struct Reference

Provides a data-transfer structure to make it easier to fill in a keys perform object's members using sscanf().

Data Fields

- unsigned int kpt_bpm_up
- unsigned int kpt_bpm_dn
- · unsigned int kpt_screenset_up
- unsigned int kpt_screenset_dn
- unsigned int kpt_set_playing_screenset
- · unsigned int kpt group on
- · unsigned int kpt group off
- unsigned int kpt_group_learn
- · unsigned int kpt_replace
- unsigned int kpt_queue
- unsigned int kpt_keep_queue
- unsigned int kpt snapshot 1
- unsigned int kpt_snapshot_2
- · unsigned int kpt start
- unsigned int kpt_stop
- · bool kpt_show_ui_sequence_key
- · bool kpt_show_ui_sequence_number
- unsigned int kpt_pattern_edit
- unsigned int kpt_event_edit
- unsigned int kpt_tap_bpm
- unsigned int kpt_pause
- unsigned int kpt_song_mode
- unsigned int kpt_toggle_jack
- unsigned int kpt_menu_mode
- unsigned int kpt_follow_transport
- unsigned int kpt_fast_forward
- · unsigned int kpt_rewind
- unsigned int kpt_pointer_position
- · unsigned int kpt toggle mutes

12.28.1 Field Documentation

12.28.1.1 kpt_bpm_up

unsigned int $seq64::keys_perform_transfer::kpt_bpm_up$

12.28.1.2 kpt_bpm_dn

unsigned int seq64::keys_perform_transfer::kpt_bpm_dn

12.28.1.3 kpt_screenset_up

unsigned int seq64::keys_perform_transfer::kpt_screenset_up

12.28.1.4 kpt_screenset_dn

unsigned int seq64::keys_perform_transfer::kpt_screenset_dn

12.28.1.5 kpt_set_playing_screenset

unsigned int seq64::keys_perform_transfer::kpt_set_playing_screenset

12.28.1.6 kpt_group_on

unsigned int $seq64::keys_perform_transfer::kpt_group_on$

12.28.1.7 kpt_group_off

unsigned int seq64::keys_perform_transfer::kpt_group_off

12.28.1.8 kpt_group_learn

unsigned int seq64::keys_perform_transfer::kpt_group_learn

12.28.1.9 kpt_replace

unsigned int seq64::keys_perform_transfer::kpt_replace

12.28.1.10 kpt_queue

unsigned int $seq64::keys_perform_transfer::kpt_queue$

12.28.1.11 kpt_keep_queue

unsigned int $seq64::keys_perform_transfer::kpt_keep_queue$

```
12.28.1.12 kpt_snapshot_1
unsigned int seq64::keys_perform_transfer::kpt_snapshot_1
12.28.1.13 kpt_snapshot_2
unsigned int seq64::keys_perform_transfer::kpt_snapshot_2
12.28.1.14 kpt_start
unsigned int seq64::keys\_perform\_transfer::kpt\_start
12.28.1.15 kpt_stop
unsigned int seq64::keys\_perform\_transfer::kpt\_stop
12.28.1.16 kpt_show_ui_sequence_key
bool seq64::keys_perform_transfer::kpt_show_ui_sequence_key
12.28.1.17 kpt_show_ui_sequence_number
bool seq64::keys_perform_transfer::kpt_show_ui_sequence_number
12.28.1.18 kpt_pattern_edit
unsigned int seq64::keys_perform_transfer::kpt_pattern_edit
12.28.1.19 kpt_event_edit
unsigned int seq64::keys_perform_transfer::kpt_event_edit
12.28.1.20 kpt_tap_bpm
unsigned int seq64::keys_perform_transfer::kpt_tap_bpm
12.28.1.21 kpt_pause
```

unsigned int seq64::keys_perform_transfer::kpt_pause

12.28.1.22 kpt_song_mode

unsigned int seq64::keys_perform_transfer::kpt_song_mode

12.28.1.23 kpt_toggle_jack

unsigned int seq64::keys_perform_transfer::kpt_toggle_jack

12.28.1.24 kpt_menu_mode

unsigned int seq64::keys_perform_transfer::kpt_menu_mode

12.28.1.25 kpt_follow_transport

unsigned int seq64::keys_perform_transfer::kpt_follow_transport

12.28.1.26 kpt_fast_forward

 ${\tt unsigned\ int\ seq64::keys_perform_transfer::kpt_fast_forward}$

12.28.1.27 kpt_rewind

unsigned int seq64::keys_perform_transfer::kpt_rewind

12.28.1.28 kpt_pointer_position

 ${\tt unsigned\ int\ seq64::keys_perform_transfer::kpt_pointer_position}$

12.28.1.29 kpt_toggle_mutes

unsigned int seq64::keys_perform_transfer::kpt_toggle_mutes

12.29 seq64::keystroke Class Reference

Encapsulates any practical keystroke.

Public Member Functions

· keystroke ()

The default constructor for class keystroke.

The principal constructor.

keystroke (const keystroke &rhs)

Provides the rote copy constructor.

• keystroke & operator= (const keystroke &rhs)

Provides the rote principal assignment operator.

• bool is press () const

'Getter' function for member m_is_press

• bool is_letter (unsigned int ch=SEQ64_KEYSTROKE_BAD_VALUE) const

'Getter' function for member m_key to test letters, handles ASCII only.

· bool is (unsigned int ch) const

Tests the key value to see if it matches the given character exactly (no case-insensitivity).

• bool is_delete () const

'Getter' function for member m_key to test for a delete-causing key.

• unsigned int key () const

'Getter' function for member m_key

void shift_lock ()

If a lower-case letter, a number, or another character on the "main" part of the keyboard, shift the m_key value to upper-case or the character shifted on a standard American keyboard.

• seq_modifier_t modifier () const

'Getter' function for member m_modifier

bool mod_control () const

'Getter' function for member m_modifier tested for Ctrl key.

• bool mod_control_shift () const

'Getter' function for member m_modifier tested for Ctrl and Shift key.

bool mod_super () const

'Getter' function for member m_modifier tested for Mod4/Super/Windows key.

Private Attributes

bool m_is_press

Determines if the key was a press or a release.

unsigned int m_key

The key that was pressed or released.

· seq_modifier_t m_modifier

The optional modifier value.

12.29.1 Detailed Description

Useful in passing more generic events to non-GUI classes.

12.29.2 Constructor & Destructor Documentation

Parameters

key	The keystroke number of the key that was pressed or released.	
press	If true, the keystroke action was a press, otherwise it was a release.	l
modkey	The modifier key combination that was pressed, if any, in the form of a bit-mask, as defined in the gdk_basic_keys module. Common mask values are SEQ64_SHIFT_MASK, SEQ64_CONTROL_MASK, SEQ64_MOD1_MASK, and SEQ64_MOD4_MASK. If no modifier, this value is SEQ64_NO_MASK.	

```
12.29.2.3 keystroke() [3/3]
seq64::keystroke::keystroke (
```

Parameters

rhs The object to be copied.

12.29.3 Member Function Documentation

const keystroke & rhs)

12.29.3.1 operator=()

Parameters

rhs The object to be assigned.

Returns

Returns the reference to the current object, for use in assignment chains.

12.29.3.2 is_press()

```
bool seq64::keystroke::is_press ( ) const [inline]
```

12.29.3.3 is_letter()

Parameters

ch An optional character to test as an ASCII letter.

Returns

If a character is not provided, true is returned if it is an upper or lower-case letter. Otherwise, true is returned if the m_key value matches the character case-insensitively.

Tricky Code

12.29.3.4 is()

Parameters

ch The character to be tested.

Returns

Returns true if $m_{key} == ch$.

12.29.3.5 is_delete()

```
bool seq64::keystroke::is_delete ( ) const [inline]
```

12.29.3.6 key()

```
unsigned int seq64::keystroke::key ( ) const [inline]
```

```
12.29.3.7 shift_lock()
```

```
void seq64::keystroke::shift_lock ( )
```

Currently also assumes the ASCII character set.

There's an oddity here: the shift of '2' is the '@' character, but seq24 seems to have treated it like the "" character. Some others were treated the same:

```
Key: 1 2 3 4 5 6 7 8 9 0
Shift: ! @ # $ % ^ & * ( )
Seq24: ! " # $ % & ' ( ) space
```

This function is meant to avoid using the Caps-Lock when picking a group-learn character in the group-learn mode.

12.29.3.8 modifier()

```
seq_modifier_t seq64::keystroke::modifier ( ) const [inline]
```

12.29.3.9 mod_control()

```
bool seq64::keystroke::mod_control ( ) const [inline]
```

12.29.3.10 mod_control_shift()

```
bool seq64::keystroke::mod_control_shift ( ) const [inline]
```

12.29.3.11 mod_super()

```
bool seq64::keystroke::mod_super ( ) const [inline]
```

12.29.4 Field Documentation

12.29.4.1 m_is_press

```
bool seq64::keystroke::m_is_press [private]
```

See the SEQ64_KEYSTROKE_PRESS and SEQ64_KEYSTROKE_RELEASE readability macros.

12.29.4.2 m_key

```
unsigned int seq64::keystroke::m_key [private]
```

Generally, the extended ASCII range (0 to 255) is supported. However, Gtk-2.x/3.x will generally support the full gamut of characters defined in the gdk_basic_keys.h module. We define minimum and maximum range macros for keystrokes that are a bit generous.

12.29.4.3 m_modifier

```
seq_modifier_t seq64::keystroke::m_modifier [private]
```

Note that SEQ64 NO MASK is our word for 0, meaning "no modifier".

12.30 seq64::lash Class Reference

This class supports LASH operations, if compiled with LASH support (i.e.

Public Member Functions

• lash (perform &p, int argc, char **argv)

This constructor calls lash_extract(), using the command-line arguments, if SEQ64_LASH_SUPPORT is enabled.

void set_alsa_client_id (int id)

Make ourselves a LASH ALSA client.

• void start ()

Process any LASH events every 250 msec, which is an arbitrarily chosen interval.

• bool process_events ()

Process LASH events.

Private Member Functions

bool init ()

Initializes LASH support, if enabled.

void handle_event (lash_event_t *conf)

Handle a LASH event.

void handle_config (lash_config_t *conf)

Handle a LASH configuration item.

Private Attributes

perform & m_perform

A hook into the single perform object in the application.

lash_client_t * m_client

Holds the client "handle" returned by the lash_init() function.

• lash args t * m lash args

Holds the command-line arguments used by the lash_init() function.

bool m_is_lash_supported

Indicates if LASH support has been compiled into the library.

12.30.1 Detailed Description

SEQ64_LASH_SUPPORT is defined). All of the ifdef skeleton work is done in this class in such a way that any other part of the code can use this class whether or not lash support is actually built in; the functions will just do nothing.

12.30.2 Constructor & Destructor Documentation

We fixed the crazy usage of argc and argv here and in the client code in the seq24 module.

Parameters

р	The perform object that needs to implement LASH support.
argc	The number of command-line arguments.
argv	The command-line arguments.

12.30.3 Member Function Documentation

char ** argv)

/param id The ALSA client ID to be set.

```
12.30.3.2 start()
void seq64::lash::start ( )

12.30.3.3 process_events()
bool seq64::lash::process_events ( )
Returns
```

Always returns true.

```
12.30.3.4 init()
bool seq64::lash::init ( ) [private]
```

Returns

Returns true if the LASH subsystem was able to be initialized, and a LASH client representative (m_client) was allocated.

12.30.3.5 handle_event()

Parameters

Provides the event to be handled.

12.30.3.6 handle_config()

```
void seq64::lash::handle\_config (
            lash_config_t * conf ) [private]
```

Currently incomplete.

Parameters

conf | Provides the configuration item to handle.

12.30.4 Field Documentation

12.30.4.1 m_perform

```
perform& seq64::lash::m_perform [private]
```

12.30.4.2 m_client

```
lash_client_t* seq64::lash::m_client [private]
```

12.30.4.3 m_lash_args

```
lash_args_t* seq64::lash::m_lash_args [private]
```

12.30.4.4 m_is_lash_supported

```
bool seq64::lash::m_is_lash_supported [private]
```

Is set to true if SEQ64_LASH_SUPPORT is defined. This variable is not used, but we will keep it around for the possibility of testing LASH support at run time.

12.31 seq64::Ifownd Class Reference

One LFO window class.

Inheritance diagram for seq64::Ifownd:

seq64::gui_window_gtk2 - m mainperf - m window x - m window y - m_redraw_period_ms - m_is_realized + gui_window_gtk2() + ~gui_window_gtk2() # perf() # quit() # redraw_period_ms() # is_realized() # scroll_hadjust() # scroll_vadjust() # scroll_hset() # scroll_vset() # on_realize() seq64::Ifownd - m_seq - m segdata - m hbox - m scale value - m_scale_range - m_scale_speed - m_scale_phase - m_scale_wave - m_value - m range - m_speed - m_phase - m_wave + Ifownd() + ~Ifownd() + toggle_visible() - scale_lfo_change() - on_focus_out_event()

Public Member Functions

- Ifownd (perform &p, sequence &seq, seqdata &sdata)
- virtual ∼lfownd ()
- void toggle_visible ()

Private Member Functions

- void scale_lfo_change ()
- bool on_focus_out_event (GdkEventFocus *p0)

Private Attributes

• sequence & m_seq

The sequence associated with this window.

• seqdata & m_seqdata

The segdata associated with this window.

- Gtk::HBox * m_hbox
- Gtk::VScale * m_scale_value
- Gtk::VScale * m_scale_range
- Gtk::VScale * m_scale_speed
- Gtk::VScale * m scale phase
- Gtk::VScale * m_scale_wave
- double m value
- double m_range
- double m_speed
- double m_phase
- wave_type_t m_wave

Additional Inherited Members

12.31.1 Detailed Description

Personally, it seems a bit of a odd duck to be included in Sequencer64, so we're thinking of a better way to manage the data managed by this window.

12.31.2 Constructor & Destructor Documentation

12.31.2.1 Ifownd()

12.31.3 Member Function Documentation

12.31.3.1 toggle_visible()

```
void seq64::lfownd::toggle_visible ( )
```

```
12.31.3.2 scale_lfo_change()
void seq64::lfownd::scale_lfo_change ( ) [private]
12.31.3.3 on_focus_out_event()
bool seq64::lfownd::on_focus_out_event (
             GdkEventFocus * p0 ) [private]
12.31.4 Field Documentation
12.31.4.1 m_seq
sequence& seq64::lfownd::m_seq [private]
12.31.4.2 m_seqdata
seqdata& seq64::lfownd::m_seqdata [private]
12.31.4.3 m_hbox
Gtk::HBox* seq64::lfownd::m_hbox [private]
12.31.4.4 m_scale_value
Gtk::VScale* seq64::lfownd::m_scale_value [private]
12.31.4.5 m_scale_range
Gtk::VScale* seq64::lfownd::m_scale_range [private]
12.31.4.6 m_scale_speed
Gtk::VScale* seq64::lfownd::m_scale_speed [private]
12.31.4.7 m_scale_phase
Gtk::VScale* seq64::lfownd::m_scale_phase [private]
12.31.4.8 m_scale_wave
Gtk::VScale* seq64::lfownd::m_scale_wave [private]
```

```
12.31.4.9 m_value
double seq64::lfownd::m_value [private]
12.31.4.10 m_range
double seq64::lfownd::m_range [private]
12.31.4.11 m_speed
double seq64::lfownd::m_speed [private]
12.31.4.12 m_phase
double seq64::lfownd::m_phase [private]
12.31.4.13 m_wave
```

12.32 seq64::maintime Class Reference

wave_type_t seq64::lfownd::m_wave [private]

This class provides the drawing of the progress bar at the top of the main window, along with two "pills" that move in time with the beat and measure.

Inheritance diagram for seq64::maintime:



Public Member Functions

- maintime (perform &p, int ppqn=SEQ64_USE_DEFAULT_PPQN)
 - This constructor sets up the colors black, white, and grey, and then allocates them.
- virtual ∼maintime ()

Let's provide a do-nothing virtual destructor.

Private Member Functions

- · maintime (const maintime &)
- maintime & operator= (const maintime &)
- int idle progress (midipulse ticks)

This function clears the window, sets the foreground to black, draws the "time" window's rectangle, and then draws a rectangle for noting the progress of the beat, and the progress for a bar.

• void on_realize ()

Handles realization of the window.

bool on expose event (GdkEventExpose *ev)

This function merely idles.

Private Attributes

· const int m beat width

Provides the divisor for ticks to produce a beat value.

· const int m bar width

Provides the divisor for ticks to produce a bar value.

const int m pill width

Provides the width of the pills, little black squares that show the progress of a beat and a bar (measure).

• const int m_box_width

The width/length of the rectangle to be drawn inside the maintime window.

· const int m box height

The height of the rectangle to be drawn inside the maintime window.

• const int m_flash_width

The width/length of the flashing rectangle to be drawn inside the maintime window.

const int m_flash_height

The height of the flashing rectangle to be drawn inside the maintime window.

· const int m flash x

The x value at which a flash should occur.

• const int m_box_less_pill

The width/length of the maintime window minus the width of the pill.

· midipulse m tick

Saves the tick value for on_expose_event().

• int m_ppqn

Provides the active PPQN value.

Friends

· class mainwnd

Additional Inherited Members

12.32.1 Detailed Description

We added a lot of members to hold the results of calculations that involve what are essentially constant. This saves CPU time, and maybe a little memory for the code to make those calculations more than once.

12.32.2 Constructor & Destructor Documentation

In the constructor you can only allocate colors; get_window() would return 0 because the windows has not yet been realized.

```
12.32.2.3 \simmaintime()
```

```
virtual seq64::maintime::~maintime ( ) [inline], [virtual]
```

12.32.3 Member Function Documentation

12.32.3.1 operator=()

12.32.3.2 idle_progress()

Idle hands do the devil's work. We should eventually support some generic coloring for "dark themes". The default coloring is better for "light themes".

Parameters

```
ticks Provides the main tick setting. This setting is provided by mainwnd(), in its timer callback.
```

Returns

Always returns 1 (it used to return "true"!).

12.32.3.3 on_realize()

```
void seq64::maintime::on_realize ( ) [private]
```

It performs the base class's on_realize() function. It then allocates some additional resources: a window, a GC (?), and it clears the window. Then it sets the default size of the window, specified by GUI constructor parameters.

12.32.3.4 on_expose_event()

We don't need the m_tick member, the function works as well if 0 is passed in. We've removed m_tick permanently.

Actually, it might be useful after all, to avoid flickering under JACK transport. Let's put it back for now. (It doesn't help, but we will leave it in, the overhead is small.)

12.32.4 Friends And Related Function Documentation

12.32.4.1 mainwnd

```
friend class mainwnd [friend]
```

12.32.5 Field Documentation

12.32.5.1 m_beat_width

```
const int seq64::maintime::m_beat_width [private]
```

Currently, this value is hardwired to 4, but will eventually be wired up as usr().midi_beat_width().

```
12.32.5.2 m_bar_width
```

```
const int seq64::maintime::m_bar_width [private]
```

Currently, this value is hardwired to 16, but will eventually be wired up as usr().midi_beat_width() * usr().midi_\circ
beats_per_bar().

12.32.5.3 m_pill_width

```
const int seq64::maintime::m_pill_width [private]
```

12.32.5.4 m_box_width

```
const int seq64::maintime::m_box_width [private]
```

This item absolutely depends on the main window being non-resizable.

```
12.32.5.5 m_box_height
const int seq64::maintime::m_box_height [private]
This item absolutely depends on the main window being non-resizable.
12.32.5.6 m_flash_width
const int seq64::maintime::m_flash_width [private]
Just a bit smaller than m box width.
12.32.5.7 m_flash_height
const int seq64::maintime::m_flash_height [private]
Just a bit smaller than m_box_width.
12.32.5.8 m_flash_x
const int seq64::maintime::m_flash_x [private]
12.32.5.9 m_box_less_pill
const int seq64::maintime::m_box_less_pill [private]
12.32.5.10 m_tick
midipulse seq64::maintime::m_tick [private]
It might actually be useful after all. And the overhead is tiny.
12.32.5.11 m_ppqn
```


While this is effectively a constant for the duration of a tune, it might change as different tunes are loaded.

int seq64::maintime::m_ppqn [private]

12.33 seq64::mainwid Class Reference

This class implements the piano roll area of the application.

Inheritance diagram for seq64::mainwid:



Public Member Functions

mainwid (perform &p)

This constructor sets all of the members.

virtual ∼mainwid ()

A rote destructor.

void set screenset (int ss, bool setperf=false)

Set the current screen-set.

Private Member Functions

· void reset ()

This function redraws everything and queues up a redraw operation.

void update_sequences_on_window ()

Updates the image of multiple sequencer/pattern slots.

void draw_pixmap_on_window ()

This function queues the blit of pixmap to window.

· void fill background window ()

This function updates the background window, clearing it.

virtual void redraw (int seq)

This virtual function, overridden from the segmenu base class, draws the the given pattern/sequence again.

virtual void seg set and edit (int segnum)

Calculates the sequence number based on the screenset and then calls the base-class function to bring up the pattern/sequence editor.

virtual void seq_set_and_eventedit (int seqnum)

Calculates the sequence number based on the screenset and then calls the base-class function to bring up the event editor

void draw_marker_on_sequence (int seq, int tick)

Does the actual drawing of one pattern/sequence position marker, a vertical progress bar.

void update_markers (int ticks)

Draw the cursors (long vertical bars) on each sequence, so that they follow the playing progress of each sequence in the mainwid (Patterns Panel).

bool valid sequence (int seq)

Common-code helper function.

void draw_sequence_on_pixmap (int seq)

This function draws a specific pattern/sequence on the pixmap located in the main window of the application, the Patterns Panel.

void draw_sequences_on_pixmap ()

This function fills the pixmap with sequences.

void draw_sequence_pixmap_on_window (int seq)

This function draws a sequence pixmap in the Patterns Panel.

int seq_from_xy (int x, int y)

Translates XY coordiinates in the Patterns Panel to a sequence number.

• int timeout ()

Provides a stock callback, because some kind of callback is needed.

void calculate_base_sizes (int seq, int &basex, int &basey)

Provides a way to calculate the base x and y size values for the pattern map.

void select_fg_bg_colors (int seqnum)

Picks the foreground and background colors based on the sequence in edit and the SEQ64_EDIT_SEQUENCE_← HIGHLIGHT macro.

· void on realize ()

For this GTK callback, on realization of window, initialize the shiz.

• bool on expose event (GdkEventExpose *ev)

Implements the GTK expose event callback.

• bool on_button_press_event (GdkEventButton *ev)

Handles a press of a mouse button in one of the sequence/pattern slots.

bool on_button_release_event (GdkEventButton *ev)

Handles a release of a mouse button.

bool on_motion_notify_event (GdkEventMotion *p0)

Handle the motion of the mouse if a mouse button is down and in another sequence and if the current sequence is not in edit mode.

• bool on_focus_in_event (GdkEventFocus *)

Handles an on-focus event.

bool on_focus_out_event (GdkEventFocus *)

Handles an out-of-focus event.

Private Attributes

· sequence m moving seq

Holds a partial copy of the sequence we are moving on the patterns panel.

• bool m_button_down

Indicates that the mouse button is still down.

bool m_moving

Indicates that we are still in the middle of a drag-and-drop operation.

int m_old_seq

Holds the sequence number of a sequence being drag-and-dropped.

• int m_screenset

Indicates the current screenset that is visible.

• long m_last_tick_x [c_max_sequence]

Holds the last active tick for each sequence, used in erasing the progress bar.

long m_last_playing [c_max_sequence]

Holds the last playing tick for each sequence.

• int m_mainwnd_rows

These values are assigned to the values given by the constants of similar names in globals.h, and we will make them parameters or user-interface configuration items later.

• int m_mainwnd_cols

Number of columns, unused in settings.

• int m_seqarea_x

Roughly with width of the main window.

· int m_seqarea_y

Roughly with height of the main window.

int m_seqarea_seq_x

To be determined.

· int m_seqarea_seq_y

To be determined.

int m_mainwid_x

To be determined.

· int m mainwid y

To be determined.

int m_mainwid_border

Main-window border, unused setting.

· int m_mainwid_spacing

Main-window spacing, unused setting.

int m_text_size_x

Text width, varies with font in use.

· int m_text_size_y

Text height, varies with font in use.

· int m max sets

The maximum number of sets, use all over.

• int m_screenset_slots

Provides a convenience variable for avoiding multiplications.

int m_screenset_offset

Provides a convenience variable for avoiding multiplications.

· int m_progress_height

Provides the height of the progress bar, to save calculations and for consistency between drawing and erasing the progress bar.

Friends

- · class mainwnd
- void update_mainwid_sequences ()

This global function in the seq64 namespace calls mainwid :: update_sequences_on_window(), if the global mainwid object exists.

Additional Inherited Members

12.33.1 Detailed Description

It inherits from gui_drawingarea_gtk2 to support the font, color, and other GUI functionality, and from seqmenu to support the right-click Edit/New/Cut right-click menu. The friend class and function are for updating the current sequence and for control via the mainwnd object.

12.33.2 Constructor & Destructor Documentation

12.33.2.1 mainwid()

And it asks for a size of c_mainwid_x by c_mainwid_y. It adds GDK masks for button presses, releases, motion, key presses, and focus changes. Also logs a self-referential singleton pointer to use for the current-edit highlighting support.

Parameters

p | Provides the reference to the all-important perform object.

12.33.2.2 ∼mainwid()

```
seq64::mainwid::\sim mainwid ( ) [virtual]
```

12.33.3 Member Function Documentation

12.33.3.1 set screenset()

The clamping algorithm for the screeset is a bit weird: if less than 0, we set m_screenset to its maximum, and if greater than the maximum, we set it to its minimum. Not sure if this matters.

Note that m screenset slots = m mainwnd rows * m mainwnd cols.

We will likely replace this with perform::set_screenset(), which recapitulates the code above completely, whereas perform::set-offset() recapitulates only the line of code immediately above it. However, note that there is a back-and-forth between setting the screenset via perform (using MIDI control) versus the GUI in the mainward class. Probably useful to add a default boolean to prevent circular manipulation.

Parameters

SS	Provides the screen-set number to set.	
setperf	If true, then also call perfrom::set_screenset(). Defaults to false. It might be better if it defaults to true.	

12.33.3.2 reset()

```
void seq64::mainwid::reset ( ) [inline], [private]

12.33.3.3 update_sequences_on_window()
```

void seq64::mainwid::update_sequences_on_window () [inline], [private]

Used by the friend class mainwnd, but also useful for our new feature to fully highlight the current sequence. Calls reset() if SEQ64_EDIT_SEQUENCE_HIGHLIGHT is defined.

```
12.33.3.4 draw_pixmap_on_window()
```

```
void seq64::mainwid::draw_pixmap_on_window ( ) [inline], [private]

12.33.3.5 fill_background_window()

void seq64::mainwid::fill_background_window ( ) [inline], [private]

12.33.3.6 redraw()

void seq64::mainwid::redraw (
```

int seqnum) [private], [virtual]

Parameters

seqnum	Provides the number of the sequence to draw.
--------	--

Implements seq64::segmenu.

12.33.3.7 seq_set_and_edit()

Used with the '=' key selection, by default.

Reimplemented from seq64::seqmenu.

12.33.3.8 seq_set_and_eventedit()

Used with the '-' key selection, by default.

Reimplemented from seq64::segmenu.

12.33.3.9 draw_marker_on_sequence()

If the sequence has no events, this function doesn't bother drawing a position marker.

Note that, when Sequencer64 first comes up, and perform::is_dirty_main() is called, no sequences exist yet. Also, currently the redraw() is hit when seq_edit() is called, but not when seq_event_edit() is called, which makes the latter not paint the in-edit highlight colors (if enabled). Why?

Parameters

seqnum	Provides the number of the sequence to draw.
tick	Provides the location to draw the marker. If pause support is compiled in (i.e. no -disable-pause in
	the configuration), then this parameter is ignored, and is replaced by the sequences' get_lask_tick()
	value. This causes correct stop/pause/play progress-bar behavior in each pattern slot.

12.33.3.10 update_markers()

Parameters

tick Starting point for drawing the markers.

12.33.3.11 valid_sequence()

Parameters

seqnum	Provides the number of the sequence to validate.
--------	--

Returns

Returns true if the sequence number is valid for the current m screenset value.

12.33.3.12 draw_sequence_on_pixmap()

The sequence is drawn only if it is in the current screen set (indicated by m_screenset). Also, we ignore the sequence if it does not exist.

Note

If only the main window is up, then the sequences just play (muted by default) – the progress bars move in each pattern. Gaps in the sequence in the Song (performance) Editor don't change the appearance of the patterns if only the main window is up. But, if the Song Editor window is up, and the song is started using the controls in the Song Editor, then the active patterns are black while playing, and white when gaps in the sequence are encountered. The muting status in the main window is ignored. The muting in the Song (performance) windows is in force. This setup holds for ALSA, but not for JACK transport.

Parameters

seqnum	Provides the number of the sequence slot that needs to be drawn. It is checked for validity before	
	usage.	

12.33.3.13 draw_sequences_on_pixmap()

```
void seq64::mainwid::draw_sequences_on_pixmap ( ) [private]
```

Please note that draw_sequence_on_pixmap() also draws the empty slots of inactive sequences, so we cannot take shortcuts here.

12.33.3.14 draw_sequence_pixmap_on_window()

The sequence is drawn only if it is in the current screen set (indicated by m_screenset. This function is used when dragging a pattern from one pattern-slot to another pattern-slot.

We have to add 1 pixel to the y height in order to avoid leaving behind a line at the bottom of an empty pattern-slot.

Parameters

seqnum	Provides the number of the sequence to draw.
--------	--

12.33.3.15 seq_from_xy()

Parameters

Χ	Provides the x coordinate.
У	Provides the y coordinate.

Returns

Returns -1 if the sequence number cannot be calculated.

```
12.33.3.16 timeout()
int seq64::mainwid::timeout ( ) [private]
```

Todo We should use this callback to display the current time in the playback.

Returns

Always returns true.

12.33.3.17 calculate_base_sizes()

The values are returned as side-effects.

Parameters

	seqnum	Provides the number of the sequence to calculate.
out	basex	A return parameter for the x coordinate of the base size.
out	basey	A return parameter for the y coordinate of the base size.

12.33.3.18 select_fg_bg_colors()

It allocates any additional resources that weren't initialized in the constructor.

This function used to call font::init(), and was the only place where the font::init() function was called. The init() function gets a color-map from the window. We need a more fool-proof was to do this!

12.33.3.20 on_expose_event()

Parameters

ev	The expose event.

Returns

Always returns true.

12.33.3.21 on_button_press_event()

If the press is a single left-click, and no Ctrl key is pressed, then this function grabs the focus, calculates the pattern/sequence over which the button press occurred, and sets the m_button_down flag if it is over a pattern. In the release event callback, this then causes the sequence arming/muting to be toggled.

If the press is a single Ctrl-left-click, this function brings up the New or Edit menu. The New menu is brought up if the grid slot is empty, and the Edit menu otherwise. Another way to bring up the same functionality is described in the next paragraph.

If the press is a double-click, it first acts just like two single-clicks (which might confuse the user at first, because it toggles the mute state twice). Then it brings up the Edit menu for the sequence. This new behavior is closer to what users have come to expect from a double-click. I miss the double-click when running seq24.

We also try to handle a Ctrl-double-click as a signal to do an event edit, instead of a sequence edit. The event editor provides a way to look at all events in detail, without having to select the type of event to see. However, this doesn't work, the event is treated like a ctrl-single-click. And we use the Alt key to enable window movement or resizing in our window manager, so that's out.

Parameters

ev Provides the parameters of the button event.

Returns

Always returns true.

12.33.3.22 on_button_release_event()

This event is a lot more complex than a press. The left button toggles playback status. The right button brings up a popup menu. If the slot is empty, then a "New" popup is presented, otherwise an "Edit" and selection popup is presented.

Also now implements the new "toggle all other patterns" action, initiated via Shift-Left-Click.

Parameters

ev Provides the parameters of the button event.

Returns

Always returns true.

Tried disabling the setting of the current sequence; it completely disables drag-n-drop. But leaving it in removes the current-sequence highlighting, which otherwise is fine. So we do it only if moving a pattern (drag-and-drop).

12.33.3.23 on_motion_notify_event()

This function moves the selected pattern to another pattern slot. The perform::delete_sequence() function sets the perform modification flag.

Parameters

ev Provides the parameters of the button event.

Returns

Always returns true.

12.33.3.24 on_focus_in_event()

Just sets the Gtk::HAS_FOCUS flag.

Returns

Always returns false.

12.33.3.25 on_focus_out_event()

Just unsets the Gtk::HAS_FOCUS flag.

Returns

Always returns false.

12.33.4 Friends And Related Function Documentation

12.33.4.1 mainwnd

```
friend class mainwnd [friend]
```

12.33.4.2 update_mainwid_sequences

```
void update_mainwid_sequences ( ) [friend]
```

It is used by other objects that can modify the currently-edited sequence shown in the mainwid (main window).

12.33.5 Field Documentation

12.33.5.1 m_moving_seq

```
sequence seq64::mainwid::m_moving_seq [private]
```

The assignment is made by sequence::partial_copy(), which behaves like the legacy seq24 code.

```
12.33.5.2 m_button_down
bool seq64::mainwid::m_button_down [private]
Used in the drag-and-drop functionality.
12.33.5.3 m_moving
bool seq64::mainwid::m_moving [private]
12.33.5.4 m_old_seq
int seq64::mainwid::m_old_seq [private]
12.33.5.5 m_screenset
int seq64::mainwid::m_screenset [private]
12.33.5.6 m_last_tick_x
long seq64::mainwid::m_last_tick_x[c_max_sequence] [private]
12.33.5.7 m_last_playing
long seq64::mainwid::m_last_playing[c_max_sequence] [private]
This doesn't seem to be used anywhere, even though values are logged, so it is macroed out.
12.33.5.8 m_mainwnd_rows
int seq64::mainwid::m_mainwnd_rows [private]
Some of them already have counterparts in the user_settings class. Number of rows, unused part of settings.
12.33.5.9 m_mainwnd_cols
int seq64::mainwid::m_mainwnd_cols [private]
12.33.5.10 m_seqarea_x
```

int seq64::mainwid::m_seqarea_x [private]

```
12.33.5.11 m_seqarea_y
int seq64::mainwid::m_seqarea_y [private]
12.33.5.12 m_seqarea_seq_x
int seq64::mainwid::m_seqarea_seq_x [private]
12.33.5.13 m_seqarea_seq_y
int seq64::mainwid::m_seqarea_seq_y [private]
12.33.5.14 m_mainwid_x
int seq64::mainwid::m_mainwid_x [private]
12.33.5.15 m_mainwid_y
int seq64::mainwid::m_mainwid_y [private]
12.33.5.16 m_mainwid_border
int seq64::mainwid::m_mainwid_border [private]
12.33.5.17 m_mainwid_spacing
int seq64::mainwid::m_mainwid_spacing [private]
12.33.5.18 m_text_size_x
int seq64::mainwid::m_text_size_x [private]
12.33.5.19 m_text_size_y
int seq64::mainwid::m_text_size_y [private]
12.33.5.20 m_max_sets
int seq64::mainwid::m_max_sets [private]
```

int seq64::mainwid::m_screenset_slots [private]

It is equal to m_mainwnd_rows * m_mainwnd_cols.

12.33.5.22 m_screenset_offset

12.33.5.21 m_screenset_slots

int seq64::mainwid::m_screenset_offset [private]

It is equally to m_screenset_slots * m_screenset.


12.33.5.23 m_progress_height

int seq64::mainwid::m_progress_height [private]

12.34 seq64::mainwnd Class Reference

This class implements the functionality of the main window of the application, except for the Patterns Panel functionality, which is implemented in the mainwid class.

Inheritance diagram for seq64::mainwnd:



Public Member Functions

- mainwnd (perform &p, bool allowperf2=true, int ppqn=SEQ64_USE_DEFAULT_PPQN)
- The constructor the main window of the application.
 virtual ~mainwnd ()

This destructor must explicitly delete some allocated resources.

• void open_file (const std::string &filename)

Opens and parses (reads) a MIDI file.

• int ppqn () const

'Getter' function for member m ppgn

• void ppqn (int ppqn)

'Setter' function for member m_ppqn We can't set the PPQN value when the mainwnd is created, we have to do it later, using this function.

Private Member Functions

void adj_callback_ss ()

This function is the callback for adjusting the screen-set value.

void adj callback bpm ()

This function is the callback for adjusting the BPM value.

void edit_callback_notepad ()

A callback function for handling an edit to the screen-set notepad.

• bool timer callback ()

This function is the GTK timer callback, used to draw our current time and BPM on_events (the main window).

void set_play_image (bool isrunning)

Changes the image used for the pause/play button.

void set songlive image (bool issong)

Changes the image used for the song/live mode button.

void start playing ()

Starts playing of the song.

void pause_playing ()

Pauses the playing of the song, leaving the progress bar where it stopped.

void stop_playing ()

Stops the playing of the song.

• void toggle_playing ()

Reverses the state of playback.

· void learn_toggle ()

Toggle the group-learn status.

• void open_performance_edit ()

Opens the Performance Editor (Song Editor).

• void open_performance_edit_2 ()

Opens the second Performance Editor (Song Editor).

• void enregister_perfedits ()

This function brings together the two perfedit objects, so that they can tell each other when to queue up a draw operation.

· void sequence key (int seq)

Use the sequence key to toggle the playing of an active pattern in the current screen-set.

void apply_song_transpose ()

Apply full song transposition, if enabled.

void update_window_title ()

Updates the title shown in the title bar of the window.

void toLower (std::string &)

Converts a string to lower-case letters.

void file_new ()

A callback function for the File / New menu entry.

• void file open ()

A callback function for the File / Open menu entry.

void file_save ()

A callback function for the File / Save menu entry.

void set_song_mute (perform::mute_op_t op)

Sets the song-mute mode.

void file_import_dialog ()

Presents a file dialog to import a MIDI file.

void options_dialog ()

Opens the File / Options dialog.

void about dialog ()

Presents a Help / About dialog.

void build_info_dialog ()

Presents a Help / Version Info dialog.

int query_save_changes ()

Queries the user to save the changes made while the application was running.

• void new_open_error_dialog ()

Tells the user to close all the edit windows first.

void file_save_as (bool do_export=false)

A callback function for the File / Save As menu entry.

• void file_exit ()

A callback function for the File / Exit menu entry.

• void new_file ()

Actually does the work of setting up for a new file.

bool save_file ()

Saves the current state in a MIDI file.

· void choose_file ()

Creates a file-chooser dialog.

• bool is_save ()

If the data is modified, then the user is queried, and the file is save if okayed.

• bool install_signal_handlers ()

Installs the signal handlers and pipe code.

• bool signal action (Glib::IOCondition condition)

Handles saving or exiting actions when signalled.

bool edit_field_has_focus () const

Check if one of the edit fields (BPM spinbutton, screenset spinbutton, or the Name field) has focus.

bool on_delete_event (GdkEventAny *ev)

This callback function handles a delete event from ...?

bool on_key_press_event (GdkEventKey *ev)

Handles a key press event.

bool on_key_release_event (GdkEventKey *ev)

Handles a key release event.

virtual void on_grouplearnchange (bool state)

Notification handler for learn mode toggle.

Static Private Member Functions

• static void handle_signal (int sig)

This function is the handler for system signals (SIGUSR1, SIGINT...) It writes a message to the pipe and leaves as soon as possible.

Private Attributes

• Gtk::Tooltips * m_tooltips

A repository for tooltips.

• Gtk::MenuBar * m menubar

Theses objects support the menu and its sub-menus.

• Gtk::Menu * m_menu_file

The File menu entry.

• Gtk::Menu * m menu edit

The (new) Edit menu entry.

• Gtk::Menu * m_menu_view

The View menu entry.

• Gtk::Menu * m menu help

The Help menu entry.

• int m ppqn

Saves the PPQN value obtained from the MIDI file (or the default value, the global ppqn, if $SEQ64_USE_DEFAUL \leftarrow T_PPQN$ was specified in reading the MIDI file.

mainwid * m_main_wid

The biggest sub-components of mainwnd.

• maintime * m_main_time

Is this the bar at the top that shows moving squares, also known as "pills"? Why yes, it is.

• perfedit * m_perf_edit

A pointer to the first song/performance editor.

perfedit * m_perf_edit_2

A pointer to an optional second song/performance editor.

options * m_options

A pointer to the program options.

Gdk::Cursor m_main_cursor

Mouse cursor?

Gtk::Image * m_image_play

Provides a pointer to hold the images for the pause/play button.

• Gtk::Button * m button learn

This button is the learn button, otherwise known as the "L" button.

• Gtk::Button * m_button_stop

Implements the red square stop button.

• Gtk::Button * m_button_play

Implements the green triangle play button.

• Gtk::Button * m_button_perfedit

The button for bringing up the Song Editor (Performance Editor).

• Gtk::Adjustment * m_adjust_bpm

The spin/adjustment controls for the BPM (beats-per-minute) value.

• Gtk::SpinButton * m_spinbutton_bpm

BPM spin-button object.

• Gtk::Adjustment * m_adjust_ss

The spin/adjustment controls for the screenset value.

• Gtk::SpinButton * m_spinbutton_ss

Screenset adjustment.

Gtk::Adjustment * m adjust load offset

The spin/adjustment controls for the load offset value.

• Gtk::SpinButton * m spinbutton load offset

Spin button for import.

Gtk::Entry * m_entry_notes

This item provides user-interface access to the screenset notepad editor.

bool m is running

Holds the current status of running, for use in display the play versus pause icon.

sigc::connection m_timeout_connect

Provides a timeout handler.

bool m_menu_mode

Indicates if the menu bar is to be greyed out or not.

• bool m_call_seq_edit

Indicates that this object is in a mode where the usual mute/unmute keystroke will instead bring up the pattern slot for editing.

• bool m_call_seq_eventedit

Indicates that this object is in a mode where the usual mute/unmute keystroke will instead bring up the pattern slot for event-editing.

Static Private Attributes

• static int m_sigpipe [2]

This small array holds the "handles" for the pipes need to intercept the system signals SIGINT and SIGUSR1, so that the application shuts down gracefully when aborted.

Additional Inherited Members

12.34.1 Constructor & Destructor Documentation

12.34.1.1 mainwnd()

This constructor is way too large; it would be nicer to provide a number of well-named initialization functions.

Parameters

р	Refers to the main performance object.	
allowperf2	Indicates if a second perfedit window should be created. This is currently a run-time option, selectable in the "user" configuration file.	
ppqn	An optional PPQN value to use in the song.	

Todo Offload most of the work into an initialization function like options does; make the perform parameter a reference; valgrind flags m tooltips as lost data, but if we try to manage it ourselves, many more leaks occur.

Edit menu items and their hot keys.

View menu items and their hot keys. It repeats the song editor edit command, just to help those whose muscle memory is already seq32-oriented.

View menu items and their hot keys.

Help menu items

Top panel items, including the logo (updated for the new version of this application) and the "timeline" progress bar.

```
12.34.1.2 \simmainwnd() seq64::mainwnd::\simmainwnd ( ) [virtual]
```

12.34.2 Member Function Documentation

```
12.34.2.1 open_file()
```

We leave the ppqn parameter set to the SEQ64_USE_DEFAULT for now, to preserve the legacy behavior of using the global ppqn, and scaling the running time against the PPQN read from the MIDI file. Later, we can provide a value like 0, that will certainly be changed by reading the MIDI file.

We don't need to specify the "oldformat" or "global sequence" parameters of the midifile constructor when reading the MIDI file, since reading handles both the old and new formats, dealing with new constructs only if they are present in the file.

Parameters

fn Provides the file-name for the MIDI file to be opened.

12.34.2.5 adj_callback_ss()

```
void seq64::mainwnd::adj_callback_ss ( ) [private]
```

Its sets the screen-set value in the Performance/Song window, the Patterns, and something about setting the text based on a screen-set notepad from the Performance/Song window. We let the perform object keep track of modifications.

12.34.2.6 adj_callback_bpm()

```
void seq64::mainwnd::adj_callback_bpm ( ) [private]
```

Let the perform object keep track of modifications.

12.34.2.7 edit_callback_notepad()

```
void seq64::mainwnd::edit_callback_notepad ( ) [private]
```

Let the perform object keep track of modifications.

12.34.2.8 timer_callback()

```
bool seq64::mainwnd::timer_callback ( ) [private]
```

It also supports the ALSA pause functionality.

Note

When Sequencer64 first starts up, and no MIDI tune is loaded, the call to mainwid::update_markers() leads to trying to do some work on sequences that don't yet exist. Also, if a sequence is changed by the event editor, we get a crash; need to find out how sequence away with the changes.

12.34.2.9 set_play_image()

```
void seq64::mainwnd::set_play_image (
    bool isrunning ) [private]
```

Parameters

isrunning

If true, set the image to the "Pause" icon, since playback is running. Otherwise, set it to the "Play" button, since playback is not running.

12.34.2.10 set_songlive_image()

Parameters

isrunning	If true, set the image to the "Pause" icon, since playback is running. Otherwise, set it to the "Play"
	button, since playback is not running.

12.34.2.11 start_playing()

```
void seq64::mainwnd::start_playing ( ) [private]
```

An accessor to perform::start_playing(). This function is actually a callback for the pause/play button. Now very similar to perfedit::start_playing(), except that the implicit songmode == false parameter is used here.

We still need to see if pause key() is workable with Stazed JACK support in force. Doesn't pause at present.

12.34.2.12 pause_playing()

```
void seq64::mainwnd::pause_playing ( ) [private]
```

Currently, it is just the same as stop_playing(), but we will get it to work.

12.34.2.13 stop_playing()

```
void seq64::mainwnd::stop_playing ( ) [private]
```

An accessor to perform's stop_playing() function. Also calls the mainwid::update_sequences_on_window() function. Not sure that we need this call, since the slots seem to update anyway. But we've noticed that, with this call in place, hitting the Stop button causes a subtle change in the appearance of the first non-empty pattern of the "allofarow.mid" file.

After the Stop button is pushed (in ALSA mode), then the Space key ("start") doesn't work properly. The song starts, then quickly stops. It doesn't matter if update_sequences_on_window() is called or not. This happens even in seq24! This bug has proven incredibly difficult to track down, still working on it.

12.34.2.14 toggle_playing()

```
void seq64::mainwnd::toggle_playing ( ) [private]
```

Meant only to be called when the "Play" button is pressed, if the pause feature has been compiled into the application.

12.34.2.15 learn_toggle()

```
void seq64::mainwnd::learn_toggle ( ) [inline], [private]
```

Simply forwards the call to perform::learn_toggle().

```
12.34.2.16 open_performance_edit()
```

```
void seq64::mainwnd::open_performance_edit ( ) [private]
```

We will let perform keep track of modifications, and not just set an is-modified flag just because we opened the song editor. We're going to centralize the modification flag in the perform object, and see if it can work.

```
12.34.2.17 open_performance_edit_2()
```

```
void seq64::mainwnd::open_performance_edit_2 ( ) [private]
```

Experiment: open a second one and see what happens. It works, but one needs to tell the other to redraw if a change is made.

12.34.2.18 enregister_perfedits()

```
void seq64::mainwnd::enregister_perfedits ( ) [private]
```

12.34.2.19 sequence_key()

12.34.2.20 apply_song_transpose()

```
void seq64::mainwnd::apply_song_transpose ( ) [private]
```

Then reset the perfedit transpose setting to 0.

12.34.2.21 update_window_title()

```
void seq64::mainwnd::update_window_title ( ) [private]
```

Note that the name of the application is obtained by the "(SEQ64_PACKAGE)" construction.

The format of the caption bar is the name of the package/application, followed by the file-specification (shortened if necessary so that the name of the file itself can be seen), ending with the PPQN value in parentheses.

12.34.2.22 toLower()

```
void seq64::mainwnd::file_new ( ) [inline], [private]
```

Note that every track of the MIDI file will be imported, even if the track is only a label track (without any MIDI events), or a very long track.

The main difference between the Open operation and the Import operation seems to be that the latter can read MIDI files into a screen-set greater than screen-set 0. No, that's not true, so far. No matter what the current screen-set setting, the import is appended after the current data in screen-set 0. Then, if it overflows that screen-set, the overflow goes into the next screen-set.

It might be nice to have the option of importing a MIDI file into a specific screen-set, for better organization, as well as being able to offset the sequence number.

Also, it is important to note that perf().clear_all() is not called by this routine, as we are merely adding to what might already be there.

```
12.34.2.28 options_dialog()
void seq64::mainwnd::options_dialog ( ) [private]
12.34.2.29 about_dialog()
```

void seq64::mainwnd::about_dialog () [private]

I (Chris) took the liberty of tacking my name at the end, and hope to have done eventually enough work to warrant having it there.

```
12.34.2.30 build_info_dialog()
void seq64::mainwnd::build_info_dialog ( ) [private]
```

It is similar to the "--version" option on the command line.

Please note that Sequencer64 will not adopt the "c_seq32_midi" type of file, because it already saves its files in a format that other sequencers should be able to read.

Stazed on the intent of the export functionality:

The original intent was to be able to play an exported song in something like TiMIDIty. After I completed things I realized that there could be an editing benefit as well. I like to record from my MIDI keyboard, improvised to a drum beat, on a long sequence (64 measures). Some is junk, but there are usually parts that I can use. In original seq24, to cut out the good or bad stuff, you would have to search the sequence by listening, then cut and move or copy and paste to a new sequence. It could be done but was always tedious. The paste box for the sequence sometimes made it difficult to find the correct note location, measure, and beat. Also, on a long sequence, you need to zoom out to see the copy location as it played, but zoom in for the precise paste location. In addition if you wanted to change the measure of the notes, it became a trial and error of copy/paste, listen, move, listen, move....

With the added Song editor feature of split trigger to mouse and copy paste trigger to mouse, you can now do all the editing from the song editor. Listen to the sequence, cut out the good or bad parts and reassemble. Move or copy all good trigger parts to the left start and delete all the bad stuff. Now you can use the song export to create the new sequence. Just mute all other tracks and export. Re-import and the new cleaned sequence is already done. Also I use it for importing drum beats from a single '32/'42 file that contains dozens of different styles with intros and endings. I like to sync two instances of '32 or '42 together with jack, then play/experiment with the different beats. If I find something I like, create the song trigger for the part I like in the drum file, export and import.

I actually do not use the song export for anything but editing.

Note that the split trigger variant of Stazed, where it doesn't just split the section in half, is not yet implemented (2016-08-05).

Parameters

do_export	If true, then just write out the file and don't change the name of the current file based on the	
	file-name the user selected. The default value of this parameter is false.	

12.34.2.34 file_exit()

```
void seq64::mainwnd::file_exit ( ) [private]

12.34.2.35 new_file()
```

```
void seq64::mainwnd::new_file ( ) [private]
```

Not sure that we need to clear the modified flag here, especially since it is now centralizeed in the perform object. Let perf().clear_all() handle it now.

```
12.34.2.36 save_file()
```

bool seq64::mainwnd::save_file () [private]

Here we specify the current value of m_ppqn, which was set when reading the MIDI file. We also let midifile tell the perform that saving worked, so that the "is modified" flag can be cleared. The midifile class is already a friend of perform.

```
12.34.2.37 choose_file()
void seq64::mainwnd::choose_file ( ) [private]
```

Change Note layk 2016-10-11 Issue #43 Added filters for upper-case MIDI-file extensions.

Returns

Returns true if the signalling was able to be completed, even if it was an unexpected signal.

12.34.2.41 edit_field_has_focus()

```
bool seq64::mainwnd::edit_field_has_focus ( ) const [private]
```

Returns

Returns true if one of the three editable/modifiable fields has the keyboard focus.

12.34.2.42 on_delete_event()

Any changed data is saved. If the pattern is playing, then it is stopped. We now use perform::is_pattern_playing().

12.34.2.43 on_key_press_event()

It also handles the control-key and modifier-key combinations matching the entries in its list of if statements.

Also, we now effectively press the CAPS LOCK key for the user if in group-learn mode, via the keystroke::shift_lock() function.

12.34.2.44 on_key_release_event()

Is this worth turning into a switch statement? Or offloading to a perform member function? The latter. Also, we now effectively press the CAPS LOCK key for the user if in group-learn mode. The function that does this is keystroke :: shift_lock().

Todo Test this functionality in old and new application.

Returns

Always returns false. This matches seg24 behavior.

12.34.2.45 on_grouplearnchange()

This handler responds to a learn-mode change from perf().

Reimplemented from seq64::performcallback.

12.34.3 Field Documentation

```
12.34.3.1 m_sigpipe
int seq64::mainwnd::m_sigpipe [static], [private]
This static member provides a couple of pipes for signalling/messaging.
12.34.3.2 m_tooltips
Gtk::Tooltips* seq64::mainwnd::m_tooltips [private]
12.34.3.3 m_menubar
Gtk::MenuBar* seq64::mainwnd::m_menubar [private]
The whole menu bar.
12.34.3.4 m_menu_file
Gtk::Menu* seq64::mainwnd::m_menu_file [private]
12.34.3.5 m_menu_edit
Gtk::Menu* seq64::mainwnd::m_menu_edit [private]
12.34.3.6 m_menu_view
Gtk::Menu* seq64::mainwnd::m_menu_view [private]
12.34.3.7 m_menu_help
Gtk::Menu* seq64::mainwnd::m_menu_help [private]
12.34.3.8 m_ppqn
```

We need it early here to be able to pass it along to child objects.

int seq64::mainwnd::m_ppqn [private]

```
12.34.3.9 m_main_wid
```

```
mainwid* seq64::mainwnd::m_main_wid [private]
```

The first is the Patterns Panel, which the mainwid helps implement. We end up sharing this object with perfedit, perfnames, and sequent in order to allow the sequent to notify the mainwid (indirectly) of the currently-edited sequence.

```
12.34.3.10 m_main_time

maintime* seq64::mainwnd::m_main_time [private]

12.34.3.11 m_perf_edit

perfedit* seq64::mainwnd::m_perf_edit [private]

12.34.3.12 m_perf_edit_2

perfedit* seq64::mainwnd::m_perf_edit_2 [private]
```

The second makes it easy to line up two different patterns that cannot be seen together on one performance editor.

```
12.34.3.13 m_options

options* seq64::mainwnd::m_options [private]

12.34.3.14 m_main_cursor

Gdk::Cursor seq64::mainwnd::m_main_cursor [private]

12.34.3.15 m_image_play

Gtk::Image* seq64::mainwnd::m_image_play [private]

12.34.3.16 m_button_learn

Gtk::Button* seq64::mainwnd::m_button_learn [private]

12.34.3.17 m_button_stop
```

Gtk::Button* seq64::mainwnd::m_button_stop [private]

```
12.34.3.18 m_button_play
```

```
Gtk::Button* seq64::mainwnd::m_button_play [private]
```

If configured to support pause, it also supports the pause pixmap and functionality.

12.34.3.19 m_button_perfedit

```
Gtk::Button* seq64::mainwnd::m_button_perfedit [private]
```

12.34.3.20 m_adjust_bpm

```
Gtk::Adjustment* seq64::mainwnd::m_adjust_bpm [private]
```

BPM adjustment object.

12.34.3.21 m_spinbutton_bpm

```
Gtk::SpinButton* seq64::mainwnd::m_spinbutton_bpm [private]
```

12.34.3.22 m_adjust_ss

```
Gtk::Adjustment* seq64::mainwnd::m_adjust_ss [private]
```

Screenset adjustment.

12.34.3.23 m_spinbutton_ss

```
Gtk::SpinButton* seq64::mainwnd::m_spinbutton_ss [private]
```

12.34.3.24 m_adjust_load_offset

```
Gtk::Adjustment* seq64::mainwnd::m_adjust_load_offset [private]
```

These controls are used in the File / Import dialog to change where the imported file will be loaded in the sequences space, which ranges from 0 to 1024 in blocks of 32 patterns.Load number for import.

12.34.3.25 m_spinbutton_load_offset

Gtk::SpinButton* seq64::mainwnd::m_spinbutton_load_offset [private]

```
12.34.3.26 m_entry_notes
```

```
Gtk::Entry* seq64::mainwnd::m_entry_notes [private]
```

This is just a long text-edit field that can be used to enter a long name or a short description of the current screenset.

12.34.3.27 m_is_running

```
bool seq64::mainwnd::m_is_running [private]
```

12.34.3.28 m_timeout_connect

```
sigc::connection seq64::mainwnd::m_timeout_connect [private]
```

12.34.3.29 m_menu_mode

```
bool seq64::mainwnd::m_menu_mode [private]
```

This is a "stazed" feature that might be generally useful.

12.34.3.30 m_call_seq_edit

```
bool seq64::mainwnd::m_call_seq_edit [private]
```

Currently, the hard-wired key for this function is the equals key.

12.34.3.31 m_call_seq_eventedit

```
bool seq64::mainwnd::m_call_seq_eventedit [private]
```

Currently, the hard-wired key for this function is the minus key.

12.35 seq64::mastermidibus Class Reference

The class that "supervises" all of the midibus objects?

Public Member Functions

• mastermidibus (int ppqn=SEQ64_USE_DEFAULT_PPQN, int bpm=c_beats_per_minute)

The mastermidibus default constructor fills the array with our busses.

∼mastermidibus ()

The destructor deletes all of the output busses, clears out the ALSA events, stops and frees the queue, and closes ALSA for this application.

• void init (int ppqn)

Initialize the mastermidibus.

snd_seq_t * get_alsa_seq () const

'Getter' function for member m_alsa_seq

• int get_num_out_buses () const

'Getter' function for member m_num_out_buses

int get_num_in_buses () const

'Getter' function for member m_num_in_buses

void set beats per minute (int bpm)

Set the BPM value (beats per minute).

void set_ppqn (int ppqn)

Set the PPQN value (parts per quarter note).

• bool filter_by_channel () const

'Getter' function for member m_filter_by_channel

void filter_by_channel (bool flag)

'Setter' function for member m filter by channel

• int get_beats_per_minute () const

'Getter' function for member m_beats_per_minute

int get_ppqn () const

'Getter' function for member m_ppqn

• std::string get_midi_out_bus_name (int bus)

Get the MIDI output buss name for the given (legal) buss number.

• std::string get_midi_in_bus_name (int bus)

Get the MIDI input buss name for the given (legal) buss number.

• void print ()

Print some information about the available MIDI output busses.

• void flush ()

Flushes our local queue events out into ALSA.

• void start ()

Starts all of the configured output busses up to m_num_out_buses.

void stop ()

Stops each of the output busses.

void clock (midipulse tick)

Generates the MIDI clock for each of the output busses.

void continue_from (midipulse tick)

Gets the output busses running again, if ALSA support is enabled.

void init_clock (midipulse tick)

Initializes the clock of each of the output busses.

• int poll_for_midi ()

Initiate a poll() on the existing poll descriptors.

bool is_more_input ()

Test the ALSA sequencer to see if any more input is pending.

bool get_midi_event (event *in)

Grab a MIDI event.

void set_sequence_input (bool state, sequence *seq)

Set the input sequence object, and set the m_dumping_input value to the given state.

void dump midi input (event in)

This function augments the recording functionality by looking for a sequence that has a matching channel number, logging the event to that sequence, and then immediately exiting.

• bool is_dumping () const

'Getter' function for member m_dumping_input

sequence * get_sequence () const

'Getter' function for member m_seq

void sysex (event *event)

Handle the sending of SYSEX events.

void port start (int client, int port)

Start the given ALSA MIDI port.

void port_exit (int client, int port)

Turn off the given port for the given client.

void play (bussbyte bus, event *e24, midibyte channel)

Handle the playing of MIDI events on the MIDI buss given by the parameter, as long as it is a legal buss number.

void set_clock (bussbyte bus, clock_e clock_type)

Set the clock for the given (legal) buss number.

clock_e get_clock (bussbyte bus)

Gets the clock setting for the given (legal) buss number.

void set_input (bussbyte bus, bool inputing)

Set the status of the given input buss, if a legal buss number.

bool get_input (bussbyte bus)

Get the input for the given (legal) buss number.

Private Attributes

snd_seq_t * m_alsa_seq

The ALSA sequencer client handle.

int m_max_busses

The maximum number of busses supported.

int m_num_out_buses

The number of output busses.

• int m_num_in_buses

The number of input busses.

midibus * m_buses_out [c_max_busses]

Output MIDI busses.

• midibus * m_buses_in [c_max_busses]

Input MIDI busses.

• midibus * m_bus_announce

MIDI buss announcer?

• bool m_buses_out_active [c_max_busses]

Active output MIDI busses.

bool m_buses_in_active [c_max_busses]

Active input MIDI busses.

bool m_buses_out_init [c_max_busses]

Output MIDI buss initialization.

• bool m buses in init [c max busses]

Input MIDI buss initialization.

clock_e m_init_clock [c_max_busses]

Clock initialization.

bool m_init_input [c_max_busses]

Input initialization?

• int m_queue

The ID of the MIDI queue.

• int m_ppqn

Resolution in parts per quarter note.

int m_beats_per_minute

BPM (beats per minute).

• int m_num_poll_descriptors

The number of descriptors for polling.

• struct pollfd * m_poll_descriptors

Points to the list of descriptors for polling.

• bool m_dumping_input

For dumping MIDI input to a sequence for recording.

• std::vector< sequence * > m_vector_sequence

Used for the new "stazed" feature of filtering MIDI channels so that a sequence gets only the channels meant for it.

· bool m filter by channel

If true, the m_vector_sequence container is used to divert incoming data to the sequence that has the channel it is meant for.

• sequence * m seq

Points to the sequence object.

• mutex m_mutex

The locking mutex.

12.35.1 Constructor & Destructor Documentation

12.35.1.1 mastermidibus()

```
seq64::mastermidibus::mastermidibus (
    int ppqn = SEQ64_USE_DEFAULT_PPQN,
    int bpm = c_beats_per_minute )
```

Parameters

ppqn	Provides the PPQN value for this object. However, in most cases, the default,
	SEQ64_USE_DEFAULT_PPQN should be specified. Then the caller of this constructor should call
	mastermidibus::set_ppqn() to set up the proper PPQN value.
bpm	Provides the beats per minute value, which defaults to c_beats_per_minute.

12.35.1.2 \sim mastermidibus()

```
seq64::mastermidibus::~mastermidibus ( )
```

Valgrind indicates we might have issues caused by the following functions:

```
    snd_config_hook_load()
    snd_config_update_r() via snd_seq_open()
    _dl_init() and other GNU function
    init_gtkmm_internals() [version 2.4]
```

12.35.2 Member Function Documentation

```
12.35.2.1 init()
void seq64::mastermidibus::init (
```

int ppqn)

It initializes 16 MIDI output busses, a hardwired constant, SEQ64_ALSA_OUTPUT_BUSS_MAX == 16. Only one MIDI input buss is initialized.

Parameters

ppqn The PPQN value to which to initialize the master MIDI buss.

```
12.35.2.2 get_alsa_seq()
snd_seq_t* seq64::mastermidibus::get_alsa_seq ( ) const [inline]

12.35.2.3 get_num_out_buses()
int seq64::mastermidibus::get_num_out_buses ( ) const [inline]

12.35.2.4 get_num_in_buses()
int seq64::mastermidibus::get_num_in_buses ( ) const [inline]

12.35.2.5 set_beats_per_minute()

void seq64::mastermidibus::set_beats_per_minute (
```

This is done by creating an ALSA tempo structure, adding tempo information to it, and then setting the ALSA sequencer object with this information.

We fill the ALSA tempo structure (snd_seq_queue_tempo_t) with the current tempo information, set the BPM value, put it in the tempo structure, and give the tempo value to the ALSA queue.

Threadsafe

Parameters

bpm Provides the beats-per-minute value to set.

12.35.2.6 set_ppqn()

```
void seq64::mastermidibus::set\_ppqn (
```

int bpm)

```
int ppqn )
```

This is done by creating an ALSA tempo structure, adding tempo information to it, and then setting the ALSA sequencer object with this information. Fills the tempo structure with the current tempo information. Then sets the ppqn value. Finally, gives the tempo structure to the ALSA queue.

Threadsafe

Parameters

```
ppqn The PPQN value to be set.
```

```
12.35.2.7 filter_by_channel() [1/2]
bool seq64::mastermidibus::filter_by_channel ( ) const [inline]

12.35.2.8 filter_by_channel() [2/2]

void seq64::mastermidibus::filter_by_channel ( bool flag ) [inline]

12.35.2.9 get_beats_per_minute()

int seq64::mastermidibus::get_beats_per_minute ( ) const [inline]

12.35.2.10 get_ppqn()

int seq64::mastermidibus::get_ppqn ( ) const [inline]

12.35.2.11 get_midi_out_bus_name()

std::string seq64::mastermidibus::get_midi_out_bus_name ( int bus )
```

Provides the output buss number. Checked before usage.

Returns

Parameters

Returns the buss name as a standard C++ string, truncated to 80-1 characters. Also contains an indication that the buss is disconnected or unconnected. If the buss number is illegal, this string is empty.

```
12.35.2.12 get_midi_in_bus_name()
```

```
bus Provides the input buss number.
```

Returns

Returns the buss name as a standard C++ string, truncated to 80-1 characters. Also contains an indication that the buss is disconnected or unconnected.

```
12.35.2.13 print()

void seq64::mastermidibus::print ( )

12.35.2.14 flush()

void seq64::mastermidibus::flush ( )

Threadsafe

12.35.2.15 start()

void seq64::mastermidibus::start ( )

Threadsafe

12.35.2.16 stop()
```

If ALSA support is enable, also drains the output, synchronizes the output queue, and then stop the queue.

Threadsafe

```
12.35.2.17 clock()
```

void seq64::mastermidibus::stop ()

Threadsafe

tick Provides the tick value with which to set the buss clock.

12.35.2.18 continue_from()

Threadsafe

Parameters

tick Provides the tick value to continue from.

12.35.2.19 init_clock()

Threadsafe

Parameters

tick Provides the tick value with which to initialize the buss clock.

12.35.2.20 poll_for_midi()

```
int seq64::mastermidibus::poll_for_midi ( )
```

Returns

Returns the result of the poll, or 0 if ALSA is not supported.

12.35.2.21 is_more_input()

```
bool seq64::mastermidibus::is_more_input ( )
```

Threadsafe

Returns

Returns true if ALSA is supported, and the returned size is greater than 0, or false otherwise.

12.35.2.22 get_midi_event()

First, a rather large buffer is allocated on the stack to hold the MIDI event data. Next, if the –alsa-manual-ports option is not in force, then we check to see if the event is a port-start, port-exit, or port-change event, and we process it, and are done.

Otherwise, we create a "MIDI event parser" and decode the MIDI event.

Threadsafe

Parameters

We will only get EVENT_SYSEX on the first packet of MIDI data; the rest we have to poll for. SysEx processing is currently disabled.

12.35.2.23 set_sequence_input()

Threadsafe

Parameters

state	Provides the dumping-input (recording) state to be set.
Olaro	- Parisage the damping input (Page and Jacobs and Jacob
sea	Provides the sequence object to be logged as the mastermidibus's sequence. Can also be used to set
364	Trovides the sequence object to be logged as the mastermidibus's sequence. Oan also be used to set
	a null pointer, to disable the sequence setting.
	a namponitor, to albabio the coquerios cotting.

12.35.2.24 dump_midi_input()

Parameters

ev The event that was recorded, passed as a copy.

12.35.2.25 is_dumping()

```
bool seq64::mastermidibus::is_dumping ( ) const [inline]
```

12.35.2.26 get_sequence()

The event is sent to all MIDI output busses.

Threadsafe

Parameters

ev Provides the event pointer to be set.

12.35.2.28 port_start()

Threadsafe Quite a lot is done during the lock!

Parameters

client	Provides the ALSA client number.
port	Provides the ALSA client port.

12.35.2.29 port_exit()

Both the input and output busses for the given client are stopped, and set to inactive.

Threadsafe

Parameters

client	The client to be matched and acted on.
port	The port to be acted on. Both parameter must be match before the buss is made inactive.

12.35.2.30 play()

```
void seq64::mastermidibus::play (
          bussbyte bus,
          event * e24,
          midibyte channel )
```

Threadsafe

Parameters

bus	The buss to start play on. Ooh, we just noticed that value should be checked before usage!
e24	The seq24 event to play on the buss.
channel	The channel on which to play the event.

12.35.2.31 set_clock()

```
void seq64::mastermidibus::set_clock (
          bussbyte bus,
          clock_e clocktype )
```

The legality checks are a little loose, however.

Threadsafe

Parameters

bus	The buss to start play on. Checked before usage.
clocktype	The type of clock to be set, either "off", "pos", or "mod", as noted in the midibus_common module.

12.35.2.32 get_clock()

Parameters

Returns

If the buss number is legal, and the buss is active, then its clock setting is returned. Otherwise, e_clock_off is returned.

12.35.2.33 set_input()

Why is another buss-count constant, and a global one at that, being used? And I thought there was only one input buss anyway! Well, there is only one ALSA input buss, but more can be used with JACK, apparently.

Threadsafe

Parameters

bus	Provides the buss number.
inputing	True if the input bus will be inputting MIDI data.

12.35.2.34 get_input()

```
bool seq64::mastermidibus::get_input (
          bussbyte bus )
```

Parameters

Returns

Always returns false.

12.35.3 Field Documentation

```
12.35.3.1 m_alsa_seq
```

```
snd_seq_t* seq64::mastermidibus::m_alsa_seq [private]
```

12.35.3.2 m_max_busses

```
int seq64::mastermidibus::m_max_busses [private]
```

Set to c_max_busses for now.

12.35.3.3 m_num_out_buses

```
int seq64::mastermidibus::m_num_out_buses [private]
```

12.35.3.4 m_num_in_buses

```
int seq64::mastermidibus::m_num_in_buses [private]
```

12.35.3.5 m_buses_out

```
midibus* seq64::mastermidibus::m_buses_out[c_max_busses] [private]
```

```
12.35.3.6 m_buses_in
midibus* seq64::mastermidibus::m_buses_in[c_max_busses] [private]
12.35.3.7 m_bus_announce
midibus* seq64::mastermidibus::m_bus_announce [private]
12.35.3.8 m_buses_out_active
\verb|bool seq64::mastermidibus::m_buses_out_active[c\_max\_busses]| [private]|
12.35.3.9 m_buses_in_active
bool seq64::mastermidibus::m_buses_in_active[c_max_busses] [private]
12.35.3.10 m buses out init
bool seq64::mastermidibus::m_buses_out_init[c_max_busses] [private]
12.35.3.11 m_buses_in_init
bool seq64::mastermidibus::m_buses_in_init[c_max_busses] [private]
12.35.3.12 m_init_clock
clock_e seq64::mastermidibus::m_init_clock[c_max_busses] [private]
12.35.3.13 m_init_input
bool seq64::mastermidibus::m_init_input[c_max_busses] [private]
12.35.3.14 m_queue
int seq64::mastermidibus::m_queue [private]
12.35.3.15 m_ppqn
int seq64::mastermidibus::m_ppqn [private]
```

```
12.35.3.16 m_beats_per_minute
int seq64::mastermidibus::m_beats_per_minute [private]
We had to lengthen this name; way too easy to confuse it with "bpm" for "beats per measure".
12.35.3.17 m_num_poll_descriptors
int seq64::mastermidibus::m_num_poll_descriptors [private]
12.35.3.18 m_poll_descriptors
struct pollfd* seq64::mastermidibus::m_poll_descriptors [private]
12.35.3.19 m_dumping_input
bool seq64::mastermidibus::m_dumping_input [private]
12.35.3.20 m_vector_sequence
std::vector<sequence *> seq64::mastermidibus::m_vector_sequence [private]
We want to make this a run-time, non-legacy option.
12.35.3.21 m_filter_by_channel
bool seq64::mastermidibus::m_filter_by_channel [private]
12.35.3.22 m_seq
sequence* seq64::mastermidibus::m_seq [private]
12.35.3.23 m_mutex
```


This object is passed to an automutex object that lends exception-safety to the mutex locking.

mutex seq64::mastermidibus::m_mutex [private]

12.36 seq64::midi_container Class Reference

This class is the abstract base class for a container of MIDI track information.

Inheritance diagram for seq64::midi container:



Public Member Functions

• midi_container (sequence &seq)

Fills in the few members of this class.

virtual ~midi_container ()

A rote constructor needed for a base class.

void fill (int tracknumber, const perform &p)

This function fills the given track (sequence) with MIDI data from the current sequence, preparatory to writing it to a file.

• virtual std::size_t size () const

Returns the size of the container, in midibytes.

· virtual bool done () const

Instead of checking for the size of the container when "emptying" it [see the midifile::write() function], use this function, which is overridden to match the type of container being used.

virtual void put (midibyte b)=0

Provides a way to add a MIDI byte into the container.

• virtual midibyte get () const =0

Provide a way to get the next byte from the container.

virtual void clear ()=0

Provides a way to clear the container.

Protected Member Functions

· unsigned int position_reset () const

'Setter' function for member m_position_for_get Sets the position to 0 and then returns that value.

· unsigned int position () const

'Getter' function for member m_position_for_get Returns the current position.

void position_increment () const

'Getter' function for member m_position_for_get Increments the current position.

Private Member Functions

• void add_variable (midipulse v)

This function masks off the lower 8 bits of the long parameter, then shifts it right 7, and, if there are still set bits, it encodes it into the buffer in reverse order.

void add long (midipulse x)

Adds a long value (a MIDI pulse/tick value) to the container.

void add_short (midishort x)

Adds a short value (two bytes) to the container.

void add_event (const event &e, midipulse deltatime)

Adds an event to the container.

• void fill_seq_number (int seq)

Fills in the sequence number.

void fill seq name (const std::string &name)

Fills in the sequence name.

- void fill_meta_track_end (midipulse deltatime)
- void fill proprietary ()

Fills in the Sequencer64-specific information for the current sequence: The MIDI buss number, the time-signature, and the MIDI channel.

void fill_time_sig_and_tempo (const perform &p)

Fill in the time-signature and tempo information.

midipulse song_fill_seq_event (const trigger &trig, midipulse prev_timestamp)

Fills in sequence events based on the trigger and events in the sequence associated with this midi container.

void song_fill_seq_trigger (const trigger &trig, midipulse len, midipulse prev_timestamp)

Fills in the trigger for the whole sequence.

Private Attributes

• sequence & m_sequence

Provide a hook into a sequence so that we can exchange data with a sequence object.

unsigned int m_position_for_get

Provides the position in the container when making a series of get() calls on the container.

Friends

· class midifile

12.36.1 Detailed Description

It is the base class for midi_list and midi_vector.

12.36.2 Constructor & Destructor Documentation

```
12.36.2.1 midi_container()
```

Parameters

sea

Provides a reference to the sequence/track for which this container holds MIDI data.

```
12.36.2.2 \sim midi_container()
```

```
virtual seq64::midi_container::~midi_container ( ) [inline], [virtual]
```

12.36.3 Member Function Documentation

12.36.3.1 fill()

```
void seq64::midi_container::fill (
    int tracknumber,
    const perform & p )
```

Note that some of the events might not come out in the same order they were stored in (we see that with program-change events). This function replaces sequence::fill_list().

Now, for sequence 0, an alternate format for writing the sequencer number chunk is "FF 00 00". But that format can only occur in the first track, and the rest of the tracks then don't need a sequence number, since it is assumed to increment. This application doesn't use that shortcut.

Stazed:

```
The "stazed" (seq32) code implements a function like this one using a function sequence::fill_proprietary_list() that we don't need for our implementation... it is part of our midi_container::fill() function.
```

Triggers:

```
Triggers are added by first calling add_variable(0), which is needed because why? Then 0xFF 0x7F is written, followed by the length value, which is the number of triggers at 3 long integers per trigger, plus the 4-byte code for triggers, c_triggers_new = 0x24240008.
```

Not threadsafe The sequence object bound to this container needs to provide the locking mechanism when calling this function.

Parameters

12.36.3.2 size()

```
tracknumber Provides the track number. This number is masked into the track information.
```

To allow other sequencers to read Seq24/Sequencer64 files, we should provide the Time Signature and Tempo meta events, in the 0th (first) track (sequence). These events must precede any "real" MIDI events. They are not included if the legacy-format option is in force.

```
virtual std::size_t seq64::midi_container::size ( ) const [inline], [virtual]
```

Must be overridden in the derived class, though not pure.

Reimplemented in seg64::midi list, and seg64::midi vector.

```
12.36.3.3 done()
```

```
virtual bool seq64::midi_container::done ( ) const [inline], [virtual]
```

Reimplemented in seq64::midi_vector, and seq64::midi_list.

```
12.36.3.4 put()
```

The original seq24 container used an std::list and a push_front operation.

Implemented in seq64::midi_vector, and seq64::midi_list.

```
12.36.3.5 get()
virtual midibyte seq64::midi_container::get ( ) const [pure virtual]
It also increments m position for get.
Implemented in seq64::midi vector, and seq64::midi list.
12.36.3.6 clear()
virtual void seq64::midi_container::clear ( ) [pure virtual]
Implemented in seq64::midi_vector, and seq64::midi_list.
12.36.3.7 position_reset()
unsigned int seq64::midi_container::position_reset ( ) const [inline], [protected]
12.36.3.8 position()
unsigned int seq64::midi_container::position ( ) const [inline], [protected]
12.36.3.9 position_increment()
void seq64::midi_container::position_increment ( ) const [inline], [protected]
12.36.3.10 add_variable()
void seq64::midi_container::add_variable (
              midipulse v ) [private]
This function "replaces" sequence::add list var().
Parameters
     The data value to be added to the current event in the MIDI container.
12.36.3.11 add_long()
void seq64::midi_container::add_long (
```

What is the difference between this function and add_list_var()? This function "replaces" sequence::add_long_list(). This was a *global* internal function called addLongList(). Let's at least make it a private member now, and hew to the naming conventions of this class.

midipulse x) [private]

x Provides the timestamp (pulse value) to be added to the container.

12.36.3.12 add_short()

Parameters

x Provides the timestamp (pulse value) to be added to the container.

12.36.3.13 add_event()

If the sequence's MIDI channel is EVENT_NULL_CHANNEL == 0xFF, then it is the copy of an SMF 0 sequence that the midi_splitter created. We want to be able to save it along with the other tracks, but won't be able to read it back if all the channels are bad. So we just use the channel from the event.

12.36.3.14 fill_seq_number()

Writes 0xFF 0x00 0x02, and then the number. This function is used in the new midifile::write_song() function, which should be ready to go by the time you're reading this.

Compare this function to the beginning of midi_container::fill().

Parameters

```
seq The sequence/track number to write.
```

12.36.3.15 fill_seq_name()

Writes 0xFF 0x03, and then the track name. This function is used in the new midifile::write_song() function, which should be ready to go by the time you're reading this.

Compare this function to the beginning of midi container::fill().

name

The sequence/track name to set. We could get this item from m_sequence, but the parameter allows the flexibility to change the name.

Then, if we're not using the legacy output format, we add the "events" for the musical key, musical scale, and the background sequence for the current sequence. Finally, if tranpose support has been compiled into the program, we add that information as well. New feature: save more sequence-specific values, if not legacy format and not saved globally. We use a single byte for the key and scale, and a long for the background sequence. We save these values only if they are different from the defaults; in most cases they will have been left alone by the user. We save per-sequence values here only if the global-background-sequence feature is not in force.

For the new "transposable" flag (tagged by the value c_transpose) we really only care about saving the value of "false", because otherwise we can assume the value is true for the given sequence, and save space by not saving it... generally only drum patterns will not be transposable.

However, for now, write it anyway for consistency with Seq32.

This function is used only for the first track, The sizes of these meta events are defined as SEQ64_TIME_TEMP← O SIZE. However, we do not have to add that value in, as it is already counted in the intrinsic size of the container.

We now make sure that the proper values are part of the perform object for usage in this particular track. For export, we cannot guarantee that the first (0th) track/sequence is exportable.

Parameters

p Provides the performance object from which we get some global MIDI parameters.

trig	The current trigger to be processed.
prev_timestamp	The time-stamp of the previous event.

Returns

The next time-stamp value is returned.

12.36.3.20 song_fill_seq_trigger()

For a song-performance, there will be only one trigger, covering the beginning to the end of the fully unlooped track.

Parameters

trig	The current trigger to be processed.
length	Provides the total length of the sequence.
prev_timestamp	The time-stamp of the previous event, which is actually the first event.

12.36.4 Friends And Related Function Documentation

12.36.4.1 midifile

```
friend class midifile [friend]
```

12.36.5 Field Documentation

12.36.5.1 m_sequence

```
sequence& seq64::midi_container::m_sequence [private]
```

12.36.5.2 m_position_for_get

```
unsigned int seq64::midi_container::m_position_for_get [mutable], [private]
```

12.37 seq64::midi_control Class Reference

This class (formerly a struct) contains the control information for sequences that make up a live set.

Public Member Functions

• midi_control ()

This default constructor creates a "zero" object.

- · bool active () const
- bool inverse_active () const
- · int status () const
- int data () const
- int min value () const
- int max_value () const
- void set (int values[6])

Not so sure if this really saves trouble for the caller.

• void set (midibyte values[6])

Not so sure if this really saves trouble for the caller.

· bool match (midibyte status, midibyte data) const

Handles a common check in the perform module.

· bool in_range (midibyte data) const

Handles a common check in the perform module.

Private Attributes

• bool m_active

Provides the value for active.

• bool m_inverse_active

Provides the value for inverse-active.

• int m_status

Provides the value for the status.

• int m data

Provides the value for the data.

• int m_min_value

Provides the minimum value for the controller.

• int m_max_value

Provides the value for the controller.

12.37.1 Detailed Description

Note that, although we've converted this to a full-fledged class, the ordering of variables and the data arrays used to fill them is very significant. See the midifile and optionsfile modules.

The perform module sets up the three following arrays for each of the MIDI controls that can be defined in the "rc" file:

```
m_midi_cc_toggle[]
m_midi_cc_on[]
m_midi_cc_off[]

These three arrays are specified in the "rc" by a line like the following:

n [0 0 0 0 0 0] [0 0 0 0 0] [0 0 0 0 0]
```

```
where n ranges from 0 to 73. Lines 0 to 31 provide controller values for
the "pattern group", one line for each of the 32 pattern slots.
Lines 32 to 63 provide controller values for
the "mute in group", one line for each of the 32 pattern slots.
The rest of the lines provide entries for control of:
BPM up, BPM down, Screen-set up, Screen-set down, Mod Replaces, Mod
Snapshot, Mod Queue, Mod gmute (group mute), Mod glearn (group learn),
and Screen-set Play.
In each of the bracketed sections, the values correspond to the members in
this order: m_active, m_inverse_active, m_status, m_data, m_min_value, and
m_max_value.
Why are the status, data, and min/max values long? A character or
midibyte would be enough. We'll fix that later, once we have tested this
stuff. We do need to convert them from long to int, though, and do that
in the scanning and output done by optionsfile.
12.37.2 Constructor & Destructor Documentation
12.37.2.1 midi_control()
seq64::midi_control::midi_control () [inline]
Every member is either false or zero.
12.37.3 Member Function Documentation
12.37.3.1 active()
bool seq64::midi_control::active ( ) const [inline]
12.37.3.2 inverse_active()
bool seq64::midi_control::inverse_active ( ) const [inline]
12.37.3.3 status()
int seq64::midi_control::status ( ) const [inline]
12.37.3.4 data()
int seq64::midi_control::data ( ) const [inline]
12.37.3.5 min_value()
int seq64::midi_control::min_value ( ) const [inline]
12.37.3.6 max_value()
int seq64::midi_control::max_value ( ) const [inline]
```

12.37.3.7 set() [1/2]

void seq64::midi_control::set (
 int values[6]) [inline]

It fits in with the big-ass sscanf() call in optionsfile.

values	Provides the six values, in an integer array, to set into the members in this order: m_active,
	m_inverse_active, m_status, m_data, m_min_value, and m_max_value.

It fits in with the usage in midifile.

Parameters

values	Provides the six values, in a byte array, to set into the members in this order: m_active, m_inverse_active,
	m_status, m_data, m_min_value, and m_max_value.

12.37.3.9 match()

Parameters

status	Provides the status byte, which is checked against m_status.
data	Provides the data byte, which is checked against m_data.

12.37.3.10 in_range()

12.37.4 Field Documentation

12.37.4.1 m_active

```
bool seq64::midi_control::m_active [private]
```

12.37.4.2 m_inverse_active

```
bool seq64::midi_control::m_inverse_active [private]
```

12.37.4.3 m_status

int seq64::midi_control::m_status [private]

12.37.4.4 m_data

int seq64::midi_control::m_data [private]

12.37.4.5 m_min_value

int seq64::midi_control::m_min_value [private]


12.37.4.6 m_max_value

int seq64::midi_control::m_max_value [private]

12.38 seq64::midi_list Class Reference

This class is the std::list implementation of the $\mbox{midi_container}.$

Inheritance diagram for seq64::midi_list:



Public Member Functions

• midi_list (sequence &seq)

This constructor fills in the members.

virtual ∼midi_list ()

A rote constructor needed for a base class.

virtual std::size_t size () const

Returns the size of the container, in midibytes.

• virtual bool done () const

For popping data from the MIDI list, we are done when the container is empty.

• virtual void put (midibyte b)

Provides a way to add a MIDI byte into the list.

• virtual midibyte get () const

Provide a way to get the next byte from the container.

• virtual void clear ()

Provides a way to clear the container.

Private Types

• typedef std::list< midibyte > CharList

Provides the type of this container.

Private Attributes

· CharList m_char_list

The container itself.

Additional Inherited Members

12.38.1 Member Typedef Documentation

```
12.38.1.1 CharList
```

```
typedef std::list<midibyte> seq64::midi_list::CharList [private]
```

This type is basically the same as the midifile::m_char_list container in the midifile module.

12.38.2 Constructor & Destructor Documentation

```
12.38.2.1 midi_list()
```

Parameters

seq The sequence/track object that is using this container.

```
12.38.2.2 ∼midi_list()
```

```
\label{list::amidi_list::amidi_list () [inline], [virtual]} virtual \ seq64::midi_list::amidi_list () \ [inline], [virtual]
```

12.38.3 Member Function Documentation

```
12.38.3.1 size()

virtual std::size_t seq64::midi_list::size ( ) const [inline], [virtual]

Reimplemented from seq64::midi_container.

12.38.3.2 done()

virtual bool seq64::midi_list::done ( ) const [inline], [virtual]

Reimplemented from seq64::midi_container.

12.38.3.3 put()
```

midibyte b) [inline], [virtual]

virtual void seq64::midi_list::put (

The original seq24 list used an std::list and a push_front operation.

Implements seq64::midi container.

```
12.38.3.4 get()
virtual midibyte seq64::midi_list::get ( ) const [inline], [virtual]
```

In this implementation, m_position_for_get is not used. The elements of the container are popped off backward! This modifies the character list, so it has to be mutable.

Implements seq64::midi_container.

```
12.38.3.5 clear()
virtual void seq64::midi_list::clear ( ) [inline], [virtual]
Implements seq64::midi_container.
```

12.38.4 Field Documentation

```
12.38.4.1 m_char_list
CharList seq64::midi_list::m_char_list [mutable], [private]
```

It has to be mutable because the const-function get() actually modifies the container when getting a byte.

12.39 seq64::midi_measures Class Reference

Provides a data structure to hold the numeric equivalent of the measures string "measures:beats:divisions" ("m:b←:d").

Public Member Functions

• midi_measures ()

Default constructor for midi_measures.

midi_measures (int measures, int beats, int divisions)

Principal constructor for midi_measures.

• int measures () const

'Getter' function for member m_measures

• void measures (int m)

'Setter' function for member m_measures

• int beats () const

'Getter' function for member m_beats

void beats (int b)

'Setter' function for member m beats

• int divisions () const

'Getter' function for member m_divisions

• void divisions (int d)

'Setter' function for member m_divisions

Private Attributes

• int m_measures

The integral number of measures in the measures-based time.

• int m_beats

The integral number of beats in the measures-based time.

· int m divisions

The integral number of divisions/pulses in the measures-based time.

12.39.1 Detailed Description

More commonly known as "bars:beats:ticks", or "BBT".

12.39.2 Constructor & Destructor Documentation

measures	Copied into the m_measures member.
beats	Copied into the m_beats member.
divisions	Copied into the m_divisions member.

12.39.3 Member Function Documentation

Parameters

m The value to which to set the number of measures. We can add validation later.

Parameters

b The value to which to set the number of beats. We can add validation later.

d The value to which to set the number of divisions. We can add validation later.

12.39.4 Field Documentation

12.39.4.1 m_measures int seq64::midi_measures::m_measures [private] 12.39.4.2 m_beats int seq64::midi_measures::m_beats [private] 12.39.4.3 m_divisions

There are two possible translations of the two bytes of a division. If the top bit of the 16 bits is 0, then the time division is in "ticks per beat" (or "pulses per quarter note"). If the top bit is 1, then the time division is in "frames per second". This member deals only with the ticks/beat definition.

12.40 seq64::midi_splitter Class Reference

int seq64::midi_measures::m_divisions [private]

This class handles the parsing and writing of MIDI files.

Public Member Functions

midi_splitter (int ppqn=SEQ64_USE_DEFAULT_PPQN)

Principal constructor.

• \sim midi_splitter ()

A rote destructor.

bool log_main_sequence (sequence &seq, int seqnum)

Logs the main sequence (an SMF 0 track) for later usage in splitting the track.

· void initialize ()

Resets the SMF 0 support variables in preparation for parsing a new MIDI file.

• void increment (int channel)

Processes a channel number by raising its flag in the m_smf0_channels[] array.

bool split (perform &p, int screenset)

This function splits an SMF 0 file, splitting all of the channels in the sequence out into separate sequences, and adding each to the perform object.

• int ppqn () const

'Getter' function for member m_ppqn Provides a way to get the actual value of PPQN used in processing the sequences when parse() was called.

· int count () const

'Getter' function for member m_smf0_channels_count

Private Member Functions

• bool split_channel (const sequence &main_seq, sequence *seq, int channel)

This function splits the given sequence into new sequences, one for each channel found in the SMF 0 track.

Private Attributes

• int m_ppqn

Provides the current value of the PPQN, which used to be constant and is now only the macro DEFAULT_PPQN.

· bool m use default ppqn

Indicates that the default PPQN is in force.

· int m smf0 channels count

Provides support for SMF 0, indicates how many channels were found in the file in a single sequence.

bool m_smf0_channels [16]

Provides support for SMF 0, holds a bool value that indicates the occurrence of a given channel.

sequence * m_smf0_main_sequence

Provides support for SMF 0, points to the initial SMF 0 sequence, from which the single-channel sequences will be created.

• int m_smf0_seq_number

Provides support for SMF 0, holds the prospective sequence number of the main (SMF 0) sequence.

12.40.1 Detailed Description

In addition to the standard MIDI tracks, it also handles some "private" or "proprietary" tracks specific to Seq24. It does not, however, handle SYSEX events.

12.40.2 Constructor & Destructor Documentation

```
12.40.2.1 midi_splitter()
```

Parameters

ppqn

Provides the initial value of the PPQN setting. It is handled differently for parsing (reading) versus writing the MIDI file.

- · Reading.
 - If set to SEQ64_USE_DEFAULT_PPQN, the legacy application behavior is used. The
 m_ppqn member is set to the default PPQN, DEFAULT_PPQN. The value read from the
 MIDI file, ppqn, is then use to scale the running-time of the sequence relative to
 DEFAULT_PPQN.
 - Otherwise, m_ppqn is set to the value read from the MIDI file. No scaling is done. Since the value gets written, specify ppqn as 0, an obviously bogus value, to get this behavior.
- Writing. This value is written to the MIDI file in the header chunk of the song. Note that the caller
 must query for the PPQN set during parsing, and pass it to the constructor when preparing to
 write the file. See how it is done in the mainwand class.

12.40.2.2 \sim midi_splitter()

```
seq64::midi_splitter::~midi_splitter ( )
```

12.40.3 Member Function Documentation

12.40.3.1 log_main_sequence()

/param seq The main sequence to be logged.

/param seqnum The sequence number of the main sequence.

/return Returns true if the main sequence's address was logged, and false if it was already logged.

12.40.3.2 initialize()

```
void seq64::midi_splitter::initialize ( )

12.40.3.3 increment()
```

If it is the first entry for that channel, m_smf0_channels_count is incremented. We won't check the channel number, to save time, until someday we segfault :-D

Parameters

channel The MIDI channel number. The caller is responsible to make sure it ranges from 0 to 15.

12.40.3.4 split()

Lastly, it adds the SMF 0 track as the last track; the user can then examine it before removing it. Is this worth the effort?

There is a little oddity, in that, if the SMF 0 track has events for only one channel, this code will still create a new sequence, as well as the main sequence. Not sure if this is worth extra code to just change the channels on the main sequence and put it into the correct track for the one channel it contains. In fact, we just want to keep it in pattern slot number 16, to keep it out of the way.

р	Provides a reference to the perform object into which sequences/tracks are to be added.
screenset	The screen-set offset to be used when loading a sequence (track) from the file.

Returns

Returns true if the parsing succeeded. Returns false if no SMF 0 main sequence was logged.

12.40.3.5 ppqn()

```
int seq64::midi_splitter::ppqn ( ) const [inline]
```

The PPQN will be either the global ppqn (legacy behavior) or the value read from the file, depending on the ppqn parameter passed to the midi_splitter constructor.

12.40.3.6 count()

```
int seq64::midi_splitter::count ( ) const [inline]
```

12.40.3.7 split_channel()

Note that the events that are read from the MIDI file have delta times. Sequencer64 converts these delta times to cumulative times. We need to preserve that here. Conversion back to delta times is needed only when saving the sequences to a file. This is done in midi_container::fill().

We have to accumulate the delta times in order to be able to set the length of the sequence in pulses.

Luckily, we don't have to worry about copying triggers, since the imported SMF 0 track won't have any Seq24/← Sequencer24 triggers.

It doesn't set the sequence number of the sequence; that is set when the sequence is added to the perform object.

Parameters

main_seq	This parameter is the whole SMF 0 track that was read from the MIDI file. It contains all of the channel data that needs to be split into separate sequences.
	and the state of t
s	Provides the new sequence that needs to have its settings made, and all of the selected channel events added to it.
channel	Provides the MIDI channel number (re 0) that marks the channel data the needs to be extracted and added to the new sequence.

Returns

Returns true if at least one event got added. If none were added, the caller should delete the sequence object represented by parameter *s*.

12.40.4 Field Documentation

```
12.40.4.1 m_ppqn
int seq64::midi_splitter::m_ppqn [private]

12.40.4.2 m_use_default_ppqn
bool seq64::midi_splitter::m_use_default_ppqn [private]
```

12.40.4.3 m_smf0_channels_count

```
int seq64::midi_splitter::m_smf0_channels_count [private]
```

SMF 1 file parsing will only warn about more than one channel found in a given sequence.

12.40.4.4 m_smf0_channels

```
bool seq64::midi_splitter::m_smf0_channels[16] [private]
```

Obviously, we don't have to worry about multiple MIDI busses.

12.40.4.5 m_smf0_main_sequence

```
sequence* seq64::midi_splitter::m_smf0_main_sequence [private]
```

12.40.4.6 m_smf0_seq_number

```
int seq64::midi_splitter::m_smf0_seq_number [private]
```

We want to be able to add that sequence last, for easier and cleaner removal of that sequence by the user.

12.41 seq64::midi_timing Class Reference

We anticipate the need to have a small structure holding the parameters needed to calculate MIDI times within an arbitrary song.

Public Member Functions

• midi_timing ()

Defaults constructor for midi_timing.

midi_timing (int bpminute, int bpmeasure, int beatwidth, int ppqn)

Principal constructor for midi_timing.

• int beats_per_minute () const

'Getter' function for member m_beats_per_minute

void beats_per_minute (int b)

'Setter' function for member m_beats_per_minute

• int beats_per_measure () const

'Getter' function for member m beats per measure

void beats_per_measure (int b)

'Setter' function for member m_beats_per_measure

int beat_width () const

'Getter' function for member m_beats_per_beat_width

void beat_width (int bw)

'Setter' function for member m_beats_per_beat_width

• int ppqn () const

'Getter' function for member m_ppqn

void ppqn (int p)

'Setter' function for member m ppgn

Private Attributes

· int m beats per minute

This value should match the BPM value selected when editing the song.

int m_beats_per_measure

This value should match the numerator value selected when editing the sequence.

· int m_beat_width

This value should match the denominator value selected when editing the sequence.

• int m ppqn

This value provides the precision of the MIDI song.

12.41.1 Detailed Description

Although Seq24/Sequencer64 currently are heavily dependent on hard-wired values, that will be rectified eventually, so let us get ready for it.

12.41.2 Constructor & Destructor Documentation

bpminute	Copied into the m_beats_per_minute member.
bpmeasure	Copied into the m_beats_per_measure member.
beatwidth	Copied into the m_beat_width member.
ppqn	Copied into the m_ppqn member.

12.41.3 Member Function Documentation

Parameters

b The value to which to set the number of beats/minute. We can add validation later.

Parameters

b The value to which to set the number of beats/measure. We can add validation later.

bw

The value to which to set the number of beats in the denominator of the time signature. We can add validation later.

Parameters

. The

The value to which to set the PPQN member. We can add validation later.

12.41.4 Field Documentation

12.41.4.1 m_beats_per_minute

```
int seq64::midi_timing::m_beats_per_minute [private]
```

This value is most commonly set to 120, but is also read from the MIDI file. This value is needed if one want to calculate durations in true time units such as seconds, but is not needed to calculate the number of pulses/ticks/divisions.

12.41.4.2 m_beats_per_measure

```
int seq64::midi_timing::m_beats_per_measure [private]
```

This value is most commonly set to 4.

12.41.4.3 m_beat_width

```
int seq64::midi_timing::m_beat_width [private]
```

This value is most commonly set to 4, meaning that the fundamental beat unit is the quarter note.

12.41.4.4 m_ppqn


```
int seq64::midi_timing::m_ppqn [private]
```

This value is most commonly set to 192, but is also read from the MIDI file. We are still working getting "non-standard" values to work.

12.42 seq64::midi_vector Class Reference

This class is the std::vector implementation of the midi_container.

Inheritance diagram for seq64::midi vector:



Public Member Functions

• midi_vector (sequence &seq)

This constructor fills in the members of this class.

virtual ∼midi_vector ()

A rote constructor needed for a base class.

- virtual std::size_t size () const
- virtual bool done () const

For iterating through the data in the MIDI vector, we are done when we've gotten the last element of the container.

virtual void put (midibyte b)

Provides a way to add a MIDI byte into the list.

• virtual midibyte get () const

Provide a way to get the next byte from the container.

• virtual void clear ()

Provides a way to clear the container.

Private Types

typedef std::vector< midibyte > CharVector

Provides the type of this container.

Private Attributes

· CharVector m char vector

The container itself.

Additional Inherited Members

12.42.1 Member Typedef Documentation

12.42.1.1 CharVector

```
typedef std::vector<midibyte> seq64::midi_vector::CharVector [private]
```

12.42.2 Constructor & Destructor Documentation

```
12.42.2.1 midi_vector()
```

Parameters

seq Provides a reference to the sequence/track for which this container holds MIDI data.

```
12.42.2.2 \simmidi_vector()
```

```
virtual seq64::midi_vector::~midi_vector ( ) [inline], [virtual]
```

12.42.3 Member Function Documentation

```
12.42.3.1 size()
virtual std::size_t seq64::midi_vector::size ( ) const [inline], [virtual]
```

Returns

Returns the size of the container, in midibytes.

Reimplemented from seq64::midi_container.

```
12.42.3.2 done()
virtual bool seq64::midi_vector::done ( ) const [inline], [virtual]
```

Returns

Returns true if the position is greater than or equal to the size of the character vector.

Reimplemented from seq64::midi_container.

The original seq24 list used an std::list and a push front operation.

Parameters

b Provides the MIDI byte to push_back() into the character vector.

Implements seq64::midi_container.

```
12.42.3.4 get()
virtual midibyte seq64::midi_vector::get ( ) const [inline], [virtual]
```

In this implementation, m_position_for_get is used. As a side-effect, the position value is incremented.

Returns

Returns the next byte in the character vector.

Implements seq64::midi_container.

```
12.42.3.5 clear()
virtual void seq64::midi_vector::clear ( ) [inline], [virtual]
Implements seq64::midi_container.

12.42.4 Field Documentation

12.42.4.1 m_char_vector

CharVector seq64::midi_vector::m_char_vector [private]
```

12.43 seq64::midibus Class Reference

Provides a class for handling the MIDI buss on Linux.

Public Member Functions

• midibus (int localclient, int destclient, int destport, snd_seq_t *seq, const char *client_name, const char *port_name, int id, int queue, int ppqn=SEQ64_USE_DEFAULT_PPQN)

Provides a constructor with client number, port number, ALSA sequencer support, name of client, name of port.

• midibus (int localclient, snd_seq_t *seq, int id, int queue, int ppqn=SEQ64_USE_DEFAULT_PPQN)

Secondary constructor.

• ∼midibus ()

A rote empty destructor.

bool init_out ()

Initialize the MIDI output port.

bool init_in ()

Initialize the MIDI input port.

• bool deinit_in ()

Deinitialize the MIDI input.

bool init_out_sub ()

Initialize the output in a different way?

• bool init_in_sub ()

Initialize the output in a different way?

• void print ()

Prints m_name.

· const std::string & get_name () const

'Getter' function for member n_name

· int get_id () const

'Getter' function for member m_id

• void play (event *e24, midibyte channel)

This play() function takes a native event, encodes it to an ALSA event, and puts it in the queue.

void sysex (event *e24)

Takes a native SYSEX event, encodes it to an ALSA event, and then puts it in the queue.

• void start ()

This function gets the MIDI clock a-runnin', if the clock type is not e_clock_off.

· void stop ()

Stop the MIDI buss.

• void clock (midipulse tick)

Generates the MIDI clock, starting at the given tick value.

• void continue_from (midipulse tick)

Continue from the given tick.

void init_clock (midipulse tick)

Initialize the clock, continuing from the given tick.

void set_clock (clock_e clocktype)

'Setter' function for member m clock type

• clock_e get_clock () const

'Getter' function for member m_clock_type

void set_input (bool inputing)

Set status to of "inputting" to the given value.

bool get_input () const

'Getter' function for member m_inputing

• void flush ()

Flushes our local queue events out into ALSA.

• int get client () const

'Getter' function for member m_dest_addr_client The address of client.

• int get_port () const

'Getter' function for member m_dest_addr_port

Static Public Member Functions

• static void set_clock_mod (int clockmod)

Set the clock mod to the given value, if legal.

• static int get_clock_mod ()

Get the clock mod value.

Private Attributes

• int m_id

The ID of the midibus object.

clock_e m_clock_type

The type of clock to use.

• bool m_inputing

TBD.

• int m_ppqn

Provides the PPQN value in force, currently a constant.

• snd_seq_t *const m_seq

ALSA sequencer client handle.

· const int m dest addr client

Destination address of client.

const int m_dest_addr_port

Destination port of client.

· const int m local addr client

Local address of client.

int m_local_addr_port

Local port of client.

• int m_queue

Another ID of the MIDI queue?

• std::string m_name

The name of the MIDI buss.

• midipulse m_lasttick

The last (most recent? final?) tick.

• mutex m_mutex

Locking mutex.

Static Private Attributes

• static int m_clock_mod

This is another name for "16 * 4".

Friends

· class mastermidibus

The master MIDI bus sets up the buss.

12.43.1 Constructor & Destructor Documentation

```
12.43.1.1 midibus() [1/2]
```

```
seq64::midibus::midibus (
    int localclient,
    int destclient,
    int destport,
    snd_seq_t * seq,
    const char * client_name,
    const char * port_name,
    int id,
    int queue,
    int ppqn = SEQ64_USE_DEFAULT_PPQN )
```

Parameters

localclient	Provides the local-client number.
destclient	Provides the destination-client number.
destport	Provides the destination-client port.
seq	Provides the ALSA sequence that will work with this buss.
client_name	Provides the client name, but this parameter is unused.
port_name	Provides the port name.
id	Provides the ID code for this bus. It is an index into the midibus definitions array, and is also used in the constructed human-readable buss name.
queue	Provides the queue ID.
ppqn	Provides the PPQN value.

12.43.1.2 midibus() [2/2]

```
seq64::midibus::midibus (
    int localclient,
    snd_seq_t * seq,
    int id,
    int queue,
    int ppqn = SEQ64_USE_DEFAULT_PPQN )
```

Similar to the principal constructor, but labels the buss by number more than by name.

Parameters

localclient	Provides the local-client number.
seq	Provides the sequence that will work with this buss.
id	Provides the ID code for this bus. It is an index into the midibus definitions array, and is also used in the constructed human-readable buss name.
queue	Provides the queue ID.
ppqn	Provides the PPQN value.

12.43.1.3 \sim midibus()

```
seq64::midibus::~midibus ()
```

12.43.2 Member Function Documentation

12.43.2.1 init_out()

```
bool seq64::midibus::init_out ( )
```

Returns

Returns true unless setting up ALSA MIDI failed in some way.

12.43.2.2 init_in()

```
bool seq64::midibus::init_in ( )
```

Returns

Returns true unless setting up ALSA MIDI failed in some way.

12.43.2.3 deinit_in()

```
bool seq64::midibus::deinit_in ( )
```

Set the input and the output ports. The destination port is actually our local port.

Returns

Returns true, unless an error occurs.

```
12.43.2.4 init_out_sub()
```

```
bool seq64::midibus::init_out_sub ( )
```

Returns

Returns true unless setting up the ALSA port failed in some way.

12.43.2.5 init_in_sub()

```
bool seq64::midibus::init_in_sub ( )
```

Returns

Returns true unless setting up the ALSA port failed in some way.

```
12.43.2.6 print()
```

```
void seq64::midibus::print ( )
```

12.43.2.7 get_name()

```
const std::string& seq64::midibus::get_name ( ) const [inline]
```

12.43.2.8 get_id()

```
int seq64::midibus::get_id ( ) const [inline]
```

12.43.2.9 play()

Threadsafe

Parameters

e24	The event to be played on this bus.
channel	The channel of the playback.

12.43.2.10 sysex()

```
void seq64::midibus::sysex (
```

```
event * e24)
```

```
e24 The event to be handled.
```

```
12.43.2.11 start()
```

```
void seq64::midibus::start ( )
```

12.43.2.12 stop()

```
void seq64::midibus::stop ( )
```

12.43.2.13 clock()

Parameters

```
tick Provides the starting tick.
```

12.43.2.14 continue_from()

Parameters

```
tick The continuing tick.
```

12.43.2.15 init_clock()

Parameters

tick The starting tick.

```
12.43.2.16 set_clock()
```

clocktype The value used to set the clock-type.

12.43.2.17 get_clock()

```
clock_e seq64::midibus::get_clock ( ) const [inline]
```

12.43.2.18 set_input()

```
void seq64::midibus::set_input (
          bool inputing )
```

If the parameter is true, then init_in() is called; otherwise, deinit_in() is called.

Parameters

```
inputing The inputing value to set.
```

```
12.43.2.19 get_input()
```

```
bool seq64::midibus::get_input ( ) const [inline]
```

12.43.2.20 flush()

```
void seq64::midibus::flush ( )
```

12.43.2.21 get_client()

```
int seq64::midibus::get_client ( ) const [inline]
```

12.43.2.22 get_port()

```
int seq64::midibus::get_port ( ) const [inline]
```

12.43.2.23 set_clock_mod()

12.43.4.6 m_seq

snd_seq_t* const seq64::midibus::m_seq [private]

clockmod If this value is not equal to 0, it is used to set the static member m clock mod. 12.43.2.24 get_clock_mod() static int seq64::midibus::get_clock_mod () [inline], [static] 12.43.3 Friends And Related Function Documentation 12.43.3.1 mastermidibus friend class mastermidibus [friend] 12.43.4 Field Documentation 12.43.4.1 m_clock_mod int seq64::midibus::m_clock_mod [static], [private] Initialize this static member. 12.43.4.2 m_id int seq64::midibus::m_id [private] 12.43.4.3 m_clock_type clock_e seq64::midibus::m_clock_type [private] 12.43.4.4 m_inputing bool seq64::midibus::m_inputing [private] 12.43.4.5 m_ppqn int seq64::midibus::m_ppqn [private]

```
12.43.4.7 m_dest_addr_client
const int seq64::midibus::m_dest_addr_client [private]
12.43.4.8 m_dest_addr_port
const int seq64::midibus::m_dest_addr_port [private]
12.43.4.9 m_local_addr_client
const int seq64::midibus::m_local_addr_client [private]
12.43.4.10 m_local_addr_port
int seq64::midibus::m_local_addr_port [private]
12.43.4.11 m_queue
int seq64::midibus::m_queue [private]
12.43.4.12 m name
std::string seq64::midibus::m_name [private]
12.43.4.13 m_lasttick
midipulse seq64::midibus::m_lasttick [private]
12.43.4.14 m_mutex
mutex seq64::midibus::m_mutex [private]
```

12.44 seq64::midifile Class Reference

This class handles the parsing and writing of MIDI files.

Public Member Functions

 midifile (const std::string &name, int ppqn=SEQ64_USE_DEFAULT_PPQN, bool oldformat=false, bool globalbgs=true)

Principal constructor.

∼midifile ()

A rote destructor.

bool parse (perform &p, int a_screen_set=0)

This function opens a binary MIDI file and parses it into sequences and other application objects.

• bool write (perform &p)

Write the whole MIDI data and Seg24 information out to the file.

- bool write song (perform &p)
- const std::string & error_message () const

'Getter' function for member m_error_message

• bool error_is_fatal () const

'Getter' function for member m_error_is_fatal

• int ppqn () const

'Getter' function for member m_ppqn Provides a way to get the actual value of PPQN used in processing the sequences when parse() was called.

Private Member Functions

• bool parse_smf_0 (perform &p, int screenset)

This function parses an SMF 0 binary MIDI file as if it were an SMF 1 file, then, if more than one MIDI channel was encountered in the sequence, splits all of the channels in the sequence out into separate sequences.

bool parse_smf_1 (perform &p, int screenset, bool is_smf0=false)

This function parses an SMF 1 binary MIDI file; it is basically the original seq24 midifile::parse() function.

midilong parse_prop_header (int file_size)

Parse the proprietary header, figuring out if it is the new format, or the legacy format, for sequencer-specific data.

· bool parse proprietary track (perform &a perf, int file size)

After all of the conventional MIDI tracks are read, we're now at the "proprietary" Seq24 data section, which describes the various features that Seq24 supports.

• int pow2 (int logbase2)

Internal function for simple calculation of a power of 2 without a lot of math.

• bool checklen (midilong len, midibyte type)

Internal function to check for and report a bad length value.

void add_trigger (sequence &seq, midishort ppqn)

Internal function to make the parser easier to read.

midilong read_long ()

Reads 4 bytes of data using read_byte().

midishort read_short ()

Reads 2 bytes of data using read_byte().

• midibyte read_byte ()

Reads 1 byte of data directly from the m_data vector, incrementing m_pos after doing so.

midilong read_varinum ()

Read a MIDI Variable-Length Value (VLV), which has a variable number of bytes.

• void write long (midilong value)

Writes 4 bytes, each extracted from the long value and shifted rightward down to byte size, using the write_byte() function.

• void write_short (midishort value)

Writes 2 bytes, each extracted from the long value and shifted rightward down to byte size, using the write_byte() function.

void read_byte_array (midibyte *b, int len)

A helper function to simplify reading midi_control data from the MIDI file.

• void write byte (midibyte c)

Writes 1 byte.

· void write varinum (midilong)

Writes a MIDI Variable-Length Value (VLV), which has a variable number of bytes.

void write_track_name (const std::string &trackname)

Writes out a track name.

std::string read_track_name ()

Reads the track name.

void write seq number (midishort seqnum)

Writes out a sequence number.

• int read_seq_number ()

Reads the sequence number.

void write track end ()

Writes out the end-of-track marker.

· bool write header (int numtracks)

We want to write:

void write_prop_header (midilong tag, long len)

Writes a "proprietary" (SeqSpec) Seq24 footer header in either the new MIDI-compliant format, or the legacy Seq24 format.

bool write_proprietary_track (perform &a_perf)

Writes out the final proprietary/SeqSpec section, using the new format if the legacy format is not in force.

· long varinum_size (long len) const

Calculates the length of a variable length value.

• long prop_item_size (long datalen) const

Calculates the size of a proprietary item, as written by the write_prop_header() function, plus whatever is called to write the data.

• long track_name_size (const std::string &trackname) const

Calculates the size of a trackname and the meta event that specifies it.

void errdump (const std::string &msg)

Helper function to emit more useful error messages.

void errdump (const std::string &msg, unsigned long p)

Helper function to emit more useful error messages for erroneous long values.

- void write_track (const midi_vector &lst)
- long seq_number_size () const

Returns the size of a sequence-number event, which is always 5 bytes, plus one byte for the delta time that precedes it.

· long track end size () const

Returns the size of a track-end event, which is always 3 bytes.

bool is_sysex_special_id (midibyte ch)

Check for special SysEx ID byte.

Private Attributes

• mutex m_mutex

Provides locking for the sequence.

• int m_file_size

Holds the size of the MIDI file.

std::string m_error_message

Holds the last error message, useful for trouble-shooting without having Sequencer64 running in a console window.

bool m_error_is_fatal

Indicates if the error should be considered fatal.

· bool m_disable_reported

Indicates that file reading has already been disabled (due to serious errors), so don't complain about it anymore.

int m_pos

Holds the position in the MIDI file.

• const std::string m_name

The unchanging name of the MIDI file.

std::vector< midibyte > m_data

This vector of characters holds our MIDI data.

std::list< midibyte > m char list

Provides a list of characters.

bool m_new_format

Use the new format for the proprietary footer section of the Seq24 MIDI file.

• bool m_global_bgsequence

Indicates to store the new key, scale, and background sequence in the global, "proprietary" section of the MIDI song.

• int m_ppqn

Provides the current value of the PPQN, which used to be constant and is now only the macro DEFAULT_PPQN.

· bool m use default ppqn

Indicates that the default PPQN is in force.

• midi_splitter m_smf0_splitter

Provides support for SMF 0.

12.44.1 Detailed Description

In addition to the standard MIDI tracks, it also handles some "private" or "proprietary" tracks specific to Seq24. It does not, however, handle SYSEX events.

12.44.2 Constructor & Destructor Documentation

12.44.2.1 midifile()

Parameters

name Provides the name of the MIDI file to be read or written.

ppqn	Provides the initial value of the PPQN setting. It is handled differently for parsing (reading) versus writing the MIDI file.
	Reading.
	 If set to SEQ64_USE_DEFAULT_PPQN, the legacy application behavior is used. The m_ppqn member is set to the default PPQN, DEFAULT_PPQN. The value read from the MIDI file, ppqn, is then use to scale the running-time of the sequence relative to DEFAULT_PPQN.
	 Otherwise, m_ppqn is set to the value read from the MIDI file. No scaling is done. Since the value gets written, specify ppqn as 0, an obviously bogus value, to get this behavior.
	 Writing. This value is written to the MIDI file in the header chunk of the song. Note that the caller must query for the PPQN set during parsing, and pass it to the constructor when preparing to write the file. See how it is done in the mainwand class.
oldformat	If true, write out the MIDI file using the old Seq24 format, instead of the new MIDI-compliant sequencer-specific format, for the seq24-specific SeqSpec tags defined in the globals module. This option is false by default. Note that this option is only used in writing; reading can handle either format transparently.
globalbgs	If true, write any non-default values of the key, scale, and background sequence to the global "proprietary" section of the MIDI file, instead of to each sequence. Note that this option is only used in writing; reading can handle either format transparently.

12.44.2.2 \sim midifile()

```
seq64::midifile::\sim midifile ( )
```

12.44.3 Member Function Documentation

12.44.3.1 parse()

In addition to the standard MIDI track data in a normal track, Seq24/Sequencer64 adds four sequencer-specific events just before the end of the track:

```
c_triggers_new: SeqSpec FF 7F 1C 24 24 00 08 00 00 ...
c_midibus: SeqSpec FF 7F 05 24 24 00 01 00
c_timesig: SeqSpec FF 7F 06 24 24 00 06 04 04
c_midich: SeqSpec FF 7F 05 24 24 00 02 06

Note that only Sequencer64 adds "FF 7F len" to the SeqSpec data.

Standard MIDI provides for port and channel specification meta events, but they are apparently considered obsolete:
```

```
Obsolete meta-event: Replacement:
MIDI port (buss): FF 21 01 po Device (port) name: FF 09 len text
MIDI channel: FF 20 01 ch
```

What do other applications use for specifying port/channel?

Note the is-modified flag: We now assume that the perform object is starting from scratch when parsing. But we let mainwind tell the perform object when to clear everything with perform::clear_all(). The mainwind does this for a new file, opening a file, but not for a file import, which might be done simply to add more MIDI tracks to the current composition. So, if parsing succeeds, all we want to do is make sure the flag is set. Parsing a file successfully is not always a modification of the setup. For instance, the first read of a MIDI file should start clean, not dirty.

SysEx notes:

Some files (e.g. Dixie04.mid) do not always encode System Exclusive messages properly for a MIDI file. Instead of a varinum length value, they are followed by extended IDs $(0x7D,\ 0x7E,\ or\ 0x7F)$.

We've covered some of those cases by disabling access to m_data if the position passes the size of the file, but we want try to bypass these odd cases properly. So we look ahead for one of these special values.

Currently, Sequencer64, like Se24, handles SysEx message only to the extend of passing them via MIDI Thru. We hope to improve on that capability.

Parameters

р	Provides a reference to the perform object into which sequences/tracks are to be added.
screenset	The screen-set offset to be used when loading a sequence (track) from the file. This value ranges
	from -31 to 0 to +31 (32 is the maximum screen-set available in Seq24). This offset is added to the sequence number read in for the sequence, to place it elsewhere in the imported tune, and locate it in a specific screen-set. If this parameter is non-zero, then we will assume that the perform data is dirty.

Returns

Returns true if the parsing succeeded. Note that the error status is saved in m_error_is_fatal, and a message (to display later) is saved in m_error_message.

12.44.3.2 write()

Also see the write song() function, for exporting to standard MIDI.

Seq24 reverses the order of some events, due to popping from its container. Not an issue here.

Parameters

p | Provides the object that will contain and manage the entire performance.

Returns

Returns true if the write operations succeeded.

The PPQN will be either the global ppqn (legacy behavior) or the value read from the file, depending on the ppqn parameter passed to the midifile constructor.

int screenset) [private]

int seq64::midifile::ppqn () const [inline]

The original sequence remains in place, in sequence slot 16 (the 17th slot). The user is responsible for deleting it if it is not needed.

Parameters

p	Provides a reference to the perform object into which sequences/tracks are to be added.
screenset	The screen-set offset to be used when loading a sequence (track) from the file.

Returns

Returns true if the parsing succeeded.

```
int screenset,
bool is_smf0 = false ) [private]
```

It assumes the file-data has already been read into memory. It also assumes that the ID, track-length, and format have already been read.

If the MIDI file contains both proprietary (c_timesig) and MIDI type 0x58 then it came from seq42 or seq32 (Stazed versions). In this case the MIDI type is parsed first (because it is listed first) then it gets overwritten by the proprietary, above.

Parameters

р	Provides a reference to the perform object into which sequences/tracks are to be added.
screenset	The screen-set offset to be used when loading a sequence (track) from the file.
is_smf0	True if we detected that the MIDI file is in SMF 0 format.

Returns

Returns true if the parsing succeeded.

12.44.3.9 parse_prop_header()

The new format creates a final track chunk, starting with "MTrk". Then comes the delta-time (here, 0), and the event. An event is a MIDI event, a SysEx event, or a Meta event.

A MIDI Sequencer Specific meta message includes either a delta time or absolute time, and the MIDI Sequencer Specific event encoded as follows:

```
0x00 0xFF 0x7F length data
```

For convenience, this function first checks the amount of file data left. If enough, then it reads a long value. If the value starts with 0×000 0xFF 0x7F, then that is a SeqSpec event, which signals usage of the new Sequencer64 "proprietary" format. Otherwise, it is probably the old format, and the long value is a control tag $(0 \times 242400 \, \text{nn})$, which can be returned immedidately.

If it is the new format, we back up to the FF, then get the next byte, which should be a 7F. If so, then we read the length (a variable length value) of the data, and then read the long value, which should be the control tag, which, again, is returned by this function.

Note

Most sequencers seem to be tolerant of both the lack of an "MTrk" marker and of the presence of an unwrapped control tag, and so can handle both the old and new formats of the final proprietary track.

file_size	The size of the data file. This value is compared against the member m_pos (the position inside
	m_data[]), to make sure there is enough data left to process.

Returns

Returns the control-tag value found. These are the values, such as c_midich, found in the globals module, that indicate the type of sequencer-specific data that comes next. If there is not enough data to process, then 0 is returned.

12.44.3.10 parse_proprietary_track()

It consists of series of tags:

```
c_midictrl
c_midiclocks
c_notes
c_bpmtag (beats per minute)
c_mutegroups
c_musickey (new, added if usr() global_seq_feature() is true)
c_musicscale (ditto)
c_backsequence (ditto)
```

(There are more tags defined in the globals module, but they are not used in this function. This doesn't quite make sense, as there are also some "triggers" values, and we're pretty sure the application uses them. Oh, it turns out that they are set up by actions performed on each sequence, and are stored as sequencer-specific ("SeqSpec") data with each track's data as held in the MIDI container for the track. See the midi_container module for more information.)

The format is (1) tag ID; (2) length of data; (3) the data.

First, we separate out this function for a little more clarity. Then we added code to handle reading both the legacy Seq24 format and the new, MIDI-compliant format. Note that even the new format is not quite correct, since it doesn't handle a MIDI manufacturer's ID, making it a single byte that is part of the data. But it does have the "MTrk" marker and track name, so that must be processed for the new format.

Now, in our "midicvt" project, we have a test MIDI file, b4uacuse-non-mtrk.midi that is good, except for having a tag "MUnk" instead of "MTrk". We should consider being more permissive, if possible. Otherwise, though, the only penality is that the "proprietary" chunk is completely skipped.

Parameters

р	The performance object that is being set via the incoming MIDI file.
file_size	The file size as determined in the parse() function.

There are also implicit parameters, with the m_pos and m_new_format member variables.

12.44.3.11 pow2()

Use for calculating the denominator of a time signature.

Parameters

logbase2	Provides the power to which 2 is to be raised. This integer is probably only rarely greater than 4
	(which represents a denominator of 16).

Returns

Returns 2 raised to the logbase2 power.

12.44.3.12 checklen()

A length of zero is now considered legal, but a "warning" message is shown. The largest value allowed within a MIDI file is 0x0FFFFFF. This limit is set to allow variable-length quantities to be manipulated as 32-bit integers.

Parameters

len	The length value to be checked, and it should be greater than 0. However, we have seen files with zero-length events, such as Lyric events (0x05).
type	The type of meta event. Used for displaying an error.

Returns

Returns true if the length parameter is valid. This now means it is simply less than 0x0FFFFFFF.

12.44.3.13 add_trigger()

Handles only c_triggers_new values, not the old c_triggers value. If m_ppqn isn't set to the default value, then we must scale these triggers accordingly, just as is done for the MIDI events.

Parameters

seq	Provides the sequence to which the trigger is to be added.
ppqn	Provides the ppqn value to use to scale the tick values if m_use_default_ppqn is true. If 0, the ppqn
	value is not used.

12.44.3.14 read_long()

```
midilong seq64::midifile::read_long ( ) [private]
```

Warning

This code looks endian-dependent and integer-size dependent.

Returns

Returns the four bytes, shifted appropriately and added together, most-significant byte first, to sum to a long value.

12.44.3.15 read_short()

```
midishort seq64::midifile::read_short ( ) [private]
```

Returns

Returns the two bytes, shifted appropriately and added together, most-significant byte first, to sum to a short value.

12.44.3.16 read_byte()

```
midibyte seq64::midifile::read_byte ( ) [private]
```

Returns

Returns the byte that was read. Returns 0 if there was an error, though there's no way for the caller to determine if this is an error or a good value.

12.44.3.17 read_varinum()

```
midilong seq64::midifile::read_varinum ( ) [private]
```

This function reads the bytes while bit 7 is set in each byte. Bit 7 is a continuation bit. See write_varinum() for more information.

Returns

Returns the accumulated values as a single number.

12.44.3.18 write_long()

Warning

This code looks endian-dependent.

x The long value to be written to the MIDI file.

12.44.3.19 write_short()

Warning

This code looks endian-dependent.

Parameters

x The short value to be written to the MIDI file.

12.44.3.20 read_byte_array()

Parameters

b	The byte array to receive the data.
len	The number of bytes in the array, and to be read.

12.44.3.21 write_byte()

The byte is written to the m_char_list member, using a call to push_back().

Parameters

c The MIDI byte to be "written".

12.44.3.22 write_varinum()

A MIDI file Variable Length Value is stored in bytes. Each byte has two parts: 7 bits of data and 1 continuation bit. The highest-order bit is set to 1 if there is another byte of the number to follow. The highest-order bit is set to 0 if this byte is the last byte in the VLV.

To recreate a number represented by a VLV, first you remove the continuation bit and then concatenate the leftover bits into a single number.

To generate a VLV from a given number, break the number up into 7 bit units and then apply the correct continuation bit to each byte.

In theory, you could have a very long VLV number which was quite large; however, in the standard MIDI file specification, the maximum length of a VLV value is 5 bytes, and the number it represents can not be larger than 4 bytes.

Here are some common cases:

```
    Numbers between 0 and 127 (0x7F) are represented by a single byte.
    0x80 is represented as "0x81 0x00".
    0x0FFFFFFFF (the largest number) is represented as "0xFF 0xFF 0xFF".
```

Also see the varinum size() function.

Parameters

value The long value to be encoded as a MIDI varinum, and written to the MIDI file.

12.44.3.23 write_track_name()

Note that we have to precede this "event" with a delta time value, set to 0. The format of the output is "0x00 0xFF 0x03 len track-name-bytes".

Parameters

```
trackname Provides the name of the track to be written to the MIDI file.
```

12.44.3.24 read_track_name()

```
std::string seq64::midifile::read_track_name ( ) [private]
```

Meant only for usage in the proprietary/SeqSpec footer track, in the new file format.

Returns

Returns the track name, or an empty string if there was a problem.

12.44.3.25 write_seq_number()

The format is "00 FF 00 02 ss ss", where "02" is actually the constant length of the data. We have to precede these values with a 0 delta time, of course.

Now, for sequence 0, an alternate format is "FF 00 00". But that format can only occur in the first track, and the rest of the tracks then don't need a sequence number, since it is assumed to increment. Our application doesn't bother with that shortcut.

Parameters

12.44.3.26 read_seq_number()

```
int seq64::midifile::read_seq_number ( ) [private]
```

Meant only for usage in the proprietary/SeqSpec footer track, in the new file format.

Returns

Returns the sequence number found, or -1 if it was not found.

12.44.3.27 write_track_end()

```
void seq64::midifile::write_track_end ( ) [private]
```

12.44.3.28 write_header()

- 0x4D54726B. The track tag "MTrk". The MIDI spec requires that software can skip over non-standard chunks. "Prop"? Would require a fix to midicvt.
- 0xaabbccdd. The length of the track. This needs to be calculated somehow.
- 0x00. A zero delta time.
- 0x7f7f. Sequence number, a special value, well out of normal range.
- · The name of the track:
 - "Seq24-Spec"
 - "Sequencer64-S"

Then follows the proprietary/SeqSpec data, written in the normal manner. Finally, tack on the track-end meta-event.

Components of final track size:

```
-# Delta time. 1 byte, always 0x00.
-# Sequence number. 5 bytes. OPTIONAL. We won't write it.
-# Track name. 3 + 10 or 3 + 15
-# Series of proprietary/SeqSpec specs:
-# Prop header:
-# If legacy format, 4 bytes.
-# Otherwise, 2 bytes + varinum_size(length) + 4 bytes.
-# Length of the prop data.
-# Track End. 3 bytes.
```

12.44.3.29 write_prop_header()

This function does not write the data. It replaces calls such as "write_long(c_midich)" in the proprietary secton of write().

The legacy format just writes the control tag (0x242400xx). The new format writes 0x00 0xFF 0x7F len 0x242400xx; the first 0x00 is the delta time.

In the new format, the 0x24 is a kind of "manufacturer ID". At http://www.midi.org/techspecs/manid. \leftarrow php we see that most manufacturer IDs start with 0x00, and are thus three bytes long, or start with codes at 0x40 and above. Similary, this site shows that no manufacturer uses 0x24:

```
http://sequence15.blogspot.com/2008/12/midi-manufacturer-ids.html
```

Warning

Currently, the manufacturer ID is not handled; it is part of the data, which can be misleading in programs that analyze MIDI files.

Parameters

control_tag	Determines the type of sequencer-specific section to be written. It should be one of the value in the globals module, such as c_midibus or c_mutegroups.
data_length	The amount of data that will be written. This parameter does not count the length of the header itself.

12.44.3.30 write_proprietary_track()

The first thing to do, for the new format only, is calculate the length of this big section of data. This was quite tricky; we tweaked and adjusted until the midicvt program handled the whole new-format file without emitting any errors.

Here's the basics of what Seq24 did for writing the data in this part of the file:

```
-# Write the c_midictrl value, then write a 0. To us, this looks like
no one wrote any code to write this data. And yet, the parsing
```

```
code can handles a non-zero value, which is the number of sequences
as a long value, not a byte. So shouldn't we write 4 bytes, not
one? Yes, indeed, we made a mistake. However, we should be
writing out the full data set as well. But not even Seq24 does
that! Perhaps they decided it was best kept in the "rc"
configuration file.
# MORE TO COME.
```

p | Provides the object that will contain and manage the entire performance.

Returns

Always returns true. No efficient way to check all of the writes that can happen. Might revisit this issue if some bug crops up.

12.44.3.31 varinum_size()

```
long seq64::midifile::varinum_size (
    long len ) const [private]
```

This function is needed when calculating the length of a track. Note that it handles only the following situations:

```
https://en.wikipedia.org/wiki/Variable-length_quantity
```

This restriction allows the calculation to be simple and fast.

```
1 byte: 0x00 to 0x7F
2 bytes: 0x80 to 0x3FFF
3 bytes: 0x4000 to 0x001FFFFF
4 bytes: 0x200000 to 0x0FFFFFFF
```

Parameters

len The long value whose length, when encoded as a MIDI varinum, is to be found.

Returns

Returns values as noted above. Anything beyond that range returns 0.

12.44.3.32 prop_item_size()

If using the new format, the length includes the sum of sequencer-specific tag (0xFF 0x7F) and the size of the variable-length value. Then, for legacy and new format, 4 bytes are added for the Seq24 MIDI control value, and then the data length is added.

data_length	Provides the data length value to be encoded.
-------------	---

Returns

Returns the length of the item size, including the delta time, meta bytes, length byes, the control tag, and the data-length itself.

12.44.3.33 track_name_size()

Parameters

Returns

Returns the length of the event, which is of the format "0x00 0xFF 0x03 len track-name-bytes".

It adds the file offset to the message.

Parameters

```
msg The main error message string, without an ending newline character.
```

Returns

The constructed string is returned as a side-effect, in case we want to pass it along to the externally-accessible error-message buffer.

12.44.3.35 errdump() [2/2]

It adds the file offset to the message.

msg	The main error message string, without an ending newline character.
value	The long value to show as part of the message.

Returns

The constructed string is returned as a side-effect, in case we want to pass it along to the externally-accessible error-message buffer.

Parameters

ch Provides the byte to be checked against 0x7D through 0x7F.

Returns

Returns true if the byte is SysEx special ID.

12.44.4 Field Documentation

12.44.4.1 m_mutex

```
mutex seq64::midifile::m_mutex [mutable], [private]
```

Made mutable for use in certain locked getter functions.

12.44.4.2 m_file_size

```
int seq64::midifile::m_file_size [private]
```

This variable was added when loading a file that caused an attempt to load data well beyond the file-size of the midicvt test file Dixie04.mid.

12.44.4.3 m_error_message

```
std::string seq64::midifile::m_error_message [private]
```

If empty, there's no pending error. Currently most useful in the parse() function.

12.44.4.4 m_error_is_fatal

```
bool seq64::midifile::m_error_is_fatal [private]
```

The caller can query for this value after getting the return value from parse().

12.44.4.5 m_disable_reported

```
bool seq64::midifile::m_disable_reported [private]
```

Once is enough.

12.44.4.6 m_pos

```
int seq64::midifile::m_pos [private]
```

This is at least a 31-bit value in the recent architectures running Linux and Windows, so it will handle up to 2 Gb of data. This member is used as the offset into the m data vector.

12.44.4.7 m_name

```
const std::string seq64::midifile::m_name [private]
```

12.44.4.8 m_data

```
std::vector<midibyte> seq64::midifile::m_data [private]
```

We could also use a string of characters, unsigned. This member is resized to the putative size of the MIDI file, in the parse() function. Then the whole file is read into it, as if it were an array. This member is an input buffer.

12.44.4.9 m_char_list

```
std::list<midibyte> seq64::midifile::m_char_list [private]
```

The class pushes each MIDI byte into this list using the write_byte() function. Also note that the write() function calls sequence::fill_list() to fill a temporary std::list<char> (!) buffer, then writes that data backwards to this member. This member is an output buffer.

12.44.4.10 m new format

```
bool seq64::midifile::m_new_format [private]
```

In the new format, each sequencer-specfic value (0x242400xx, as defined in the globals module) is preceded by the sequencer-specific prefix, 0xFF 0x7F len id/date). By default, the new format is used, but the user can specify the —legacy (-l) option, or make a soft link to the sequence24 binary called "seq24", to write the data in the old format. [We will eventually add the —legacy option to the "rc" configuration file.] Note that reading can handle either format transparently.

12.44.4.11 m_global_bgsequence

```
bool seq64::midifile::m_global_bgsequence [private]
```

12.44.4.12 m_ppqn

```
int seq64::midifile::m_ppqn [private]
```

12.44.4.13 m_use_default_ppqn

```
bool seq64::midifile::m_use_default_ppqn [private]
```

12.44.4.14 m_smf0_splitter


```
midi_splitter seq64::midifile::m_smf0_splitter [private]
```

This object holds all of the information needed to split a multi-channel sequence.

12.45 seq64::mutex Class Reference

The mutex class provides a simple wrapper for the pthread_mutex_t type used as a recursive mutex.

Inheritance diagram for seq64::mutex:



Public Member Functions

• mutex ()

The constructor assigns the recursive mutex to the local locking mutex.

· void lock () const

Lock the mutex.

· void unlock () const

Unlock the mutex.

Protected Attributes

• pthread_mutex_t m_mutex_lock

Provides a mutex lock usable by a single module or class.

Static Private Attributes

• static const pthread_mutex_t sm_recursive_mutex

Provides a recursive mutex that can be used by the whole application, and is, apparently.

12.45.1 Constructor & Destructor Documentation

```
12.45.1.1 mutex()
seq64::mutex::mutex ( )
```

12.45.2 Member Function Documentation

```
12.45.2.1 lock()

void seq64::mutex::lock ( ) const

12.45.2.2 unlock()

void seq64::mutex::unlock ( ) const
```

12.45.3 Field Documentation

12.45.3.1 sm_recursive_mutex

```
const pthread_mutex_t seq64::mutex::sm_recursive_mutex [static], [private]
```

Define the static recursive mutex and its condition variable.

```
12.45.3.2 m_mutex_lock
pthread_mutex_t seq64::mutex::m_mutex_lock [mutable], [protected]
```

However, this mutex ends up being a copy of the static sm_recursive_mutex (and, of course, a different "object").

12.46 seq64::editable_event::name_value_t Struct Reference

Provides a type that contains the pair of values needed for the various lookup maps that are needed to manage editable events.

Data Fields

- unsigned short event_value
 - Holds a midibyte value (0x00 to 0xFF) or SEQ64_END_OF_MIDIBYTE_TABLE to indicate the end of an array of name_value_t items.
- std::string event_name

Holds the human-readable name for an event code or other numeric value in an array of name_value_t items.

12.46.1 Field Documentation

12.46.1.1 event_value

```
unsigned short seq64::editable_event::name_value_t::event_value
```

12.46.1.2 event_name

```
std::string seq64::editable_event::name_value_t::event_name
```

12.47 seq64::options Class Reference

This class supports a full tabbed options dialog.

Inherits Dialog.

Public Member Functions

options (Gtk::Window &parent, perform &p)

Private Types

```
    enum button {
    e_jack_transport,
    e_jack_master,
    e_jack_master_cond,
    e_jack_start_mode_live,
    e_jack_start_mode_song,
    e_jack_connect,
    e_jack_disconnect }
```

Defines buttons indices or IDs for some controls related to JACK.

Private Member Functions

```
• perform & perf ()
```

'Getter' function for member m_mainperf

- void clock_callback_off (int bus, Gtk::RadioButton *button)
- void clock_callback_on (int bus, Gtk::RadioButton *button)
- void clock_callback_mod (int bus, Gtk::RadioButton *button)
- void clock_mod_callback (Gtk::Adjustment *adj)
- void input_callback (int bus, Gtk::Button *button)
- void filter_callback (Gtk::Button *button)
- void transport_callback (button type, Gtk::Button *button)
- void mouse_seq24_callback (Gtk::RadioButton *)
- void mouse_fruity_callback (Gtk::RadioButton *)
- void mouse_mod4_callback (Gtk::CheckButton *)
- void mouse_snap_split_callback (Gtk::CheckButton *)
- void lash_support_callback (Gtk::CheckButton *)
- void add_midi_clock_page ()
- void add_midi_input_page ()
- void add_keyboard_page ()
- void add_extended_keys_page ()
- void add_mouse_page ()
- void add_jack_sync_page ()

Private Attributes

• Gtk::Tooltips * m_tooltips

A repository for GTK tooltip support.

· perform & m_mainperf

The performance object to which some of these options apply.

• Gtk::Button * m_button_ok

The famous "OK" button's pointer.

• Gtk::CheckButton * m_button_jack_transport

Main JACK transport selection.

• Gtk::CheckButton * m_button_jack_master

Main JACK transport master selection.

• Gtk::CheckButton * m_button_jack_master_cond

Main JACK transport master-conditional selection.

• Gtk::Button * m_button_jack_connect

JACK Connect button, which we need to enable/disable for clarity and some additional safety.

Gtk::Button * m_button_jack_disconnect

JACK Disonnect button, which we need to enable/disable for clarity and some additional safety.

• Gtk::Notebook * m notebook

Not sure yet what this notebook is for.

12.47.1 Member Enumeration Documentation

12.47.1.1 button

```
enum seq64::options::button [private]
```

These values are handled in options::transport_callback(). Some of them set JACK-related values in the rc_settings object, while the others set up or tear down the JACK support of sequencer64.

The JACK Transport settings are a little messy. They should be radio buttons, and control each other's settings. Currently, if the user wants to set up for JACK Master, the JACK Transport button must also be checked.

Enumerator

e_jack_transport	Turns on the "with JACK Transport" option, rc_settings::with_jack_transport().
e_jack_master	Turns on the "with JACK Master" option, rc_settings::with_jack_master(). If
	another application is already JACK Master, this will fail.
e_jack_master_cond	Turns on the "with JACK Master" option rc_settings::with_jack_master_cond().
	This option makes sequencer64 the JACK Master conditionally, that is, if no other
	application has claimed that role.
e_jack_start_mode_live	Doesn't directly do anything; the live mode versus song mode is set by the
	e_jack_start_mode_song value.
e_jack_start_mode_song	Sets the "JACK start mode" value to true, which means that sequencer64 is in
	song mode. This value is obtained via rc_settings::song_start_mode(). It will
	eventually be the start mode that applies to either ALSA or JACK playback.
e_jack_connect	Causes the perform object's JACK initialization function, perform::init_jack(), to be
	called.
e_jack_disconnect	Causes the perform object's JACK deinitialization function, perform::deinit_jack(),
	to be called.

12.47.2 Constructor & Destructor Documentation

```
12.47.2.1 options()
seq64::options::options (
             Gtk::Window & parent,
             perform & p )
12.47.3 Member Function Documentation
12.47.3.1 perf()
perform& seq64::options::perf ( ) [inline], [private]
12.47.3.2 clock_callback_off()
void seq64::options::clock_callback_off (
             int bus,
             Gtk::RadioButton * button ) [private]
12.47.3.3 clock_callback_on()
void seq64::options::clock_callback_on (
             int bus,
             Gtk::RadioButton * button ) [private]
12.47.3.4 clock_callback_mod()
void seq64::options::clock_callback_mod (
             int bus,
             Gtk::RadioButton * button ) [private]
12.47.3.5 clock_mod_callback()
void seq64::options::clock_mod_callback (
             Gtk::Adjustment * adj ) [private]
12.47.3.6 input_callback()
void seq64::options::input_callback (
             int bus,
```

Gtk::Button * button) [private]

```
12.47.3.7 filter_callback()
void seq64::options::filter_callback (
             Gtk::Button * button ) [private]
12.47.3.8 transport callback()
void seq64::options::transport_callback (
            button type,
             Gtk::Button * button ) [private]
12.47.3.9 mouse_seq24_callback()
void seq64::options::mouse_seq24_callback (
             Gtk::RadioButton * ) [private]
12.47.3.10 mouse_fruity_callback()
void seq64::options::mouse_fruity_callback (
             Gtk::RadioButton * ) [private]
12.47.3.11 mouse_mod4_callback()
void seq64::options::mouse_mod4_callback (
             Gtk::CheckButton * ) [private]
12.47.3.12 mouse_snap_split_callback()
void seq64::options::mouse_snap_split_callback (
             Gtk::CheckButton * ) [private]
12.47.3.13 lash_support_callback()
void seq64::options::lash_support_callback (
             Gtk::CheckButton * ) [private]
12.47.3.14 add_midi_clock_page()
void seq64::options::add_midi_clock_page ( ) [private]
12.47.3.15 add_midi_input_page()
void seq64::options::add_midi_input_page ( ) [private]
```

```
12.47.3.16 add_keyboard_page()
void seq64::options::add_keyboard_page ( ) [private]
12.47.3.17 add_extended_keys_page()
void seq64::options::add_extended_keys_page ( ) [private]
12.47.3.18 add_mouse_page()
void seq64::options::add_mouse_page ( ) [private]
12.47.3.19 add_jack_sync_page()
void seq64::options::add_jack_sync_page ( ) [private]
12.47.4 Field Documentation
12.47.4.1 m_tooltips
Gtk::Tooltips* seq64::options::m_tooltips [private]
12.47.4.2 m_mainperf
perform& seq64::options::m_mainperf [private]
12.47.4.3 m_button_ok
Gtk::Button* seq64::options::m_button_ok [private]
12.47.4.4 m_button_jack_transport
Gtk::CheckButton* seq64::options::m_button_jack_transport [private]
12.47.4.5 m_button_jack_master
Gtk::CheckButton* seq64::options::m_button_jack_master [private]
12.47.4.6 m_button_jack_master_cond
Gtk::CheckButton* seq64::options::m_button_jack_master_cond [private]
```

12.47.4.7 m_button_jack_connect

```
Gtk::Button* seq64::options::m_button_jack_connect [private]
```

12.47.4.8 m_button_jack_disconnect

```
Gtk::Button* seq64::options::m_button_jack_disconnect [private]
```

12.47.4.9 m_notebook


Gtk::Notebook* seq64::options::m_notebook [private]

Must be a GTK thang.

12.48 seq64::optionsfile Class Reference

Provides a file for reading and writing the application' main configuration file.

Inheritance diagram for seq64::optionsfile:



Public Member Functions

• optionsfile (const std::string &name)

Principal constructor.

∼optionsfile ()

A rote destructor.

• bool parse (perform &perf)

Parse the ~/.seq24rc or ~/.config/sequencer64/sequencer64.rc file.

bool write (const perform &perf)

This options-writing function is just about as complex as the options-reading function.

Private Member Functions

• bool error_message (const std::string §ionname)

Helper function for error-handling.

Additional Inherited Members

12.48.1 Detailed Description

The settings that are passed around are provided or used by the perform class.

12.48.2 Constructor & Destructor Documentation

12.48.2.1 optionsfile()

Parameters

name Provides the name of the options file; this is usually a full path file-specification.

12.48.2.2 \sim optionsfile()

```
seq64::optionsfile::\sim optionsfile ()
```

12.48.3 Member Function Documentation

12.48.3.1 parse()

[midi-control]

Get the number of sequence definitions provided in the [midi-control] section. Ranges from 32 on up. Then read in all of the sequence lines. The first 32 apply to the first screen set. There can also be a comment line "# mute in group" followed by 32 more lines. Then there are addditional comments and single lines for BPM up, BPM down, Screen Set Up, Screen Set Down, Mod Replace, Mod Snapshot, Mod Queue, Mod Gmute, Mod Glearn, and Screen Set Play. These are all forms of MIDI automation useful to control the playback while not sitting near the computer.

[mute-group]

The mute-group starts with a line that indicates up to 32 mute-groups are defined. A common value is 1024, which means there are 32 groups times 32 keys. But this value is currently thrown away. This value is followed by 32 lines of data, each contained 4 sets of 8 settings. See the seq24-doc project on GitHub for a much more detailed description of this section.

[midi-clock]

The MIDI-clock section defines the clocking value for up to 16 output busses. The first number, 16, indicates how many busses are specified. Generally, these busses are shown to the user with names such as "[1] seq24 1".

[keyboard-control]

The keyboard control defines the keys that will toggle the stage of each of up to 32 patterns in a pattern/sequence box. These keys are displayed in each box as a reminder. The first number specifies the Key number, and the second number specifies the Sequence number.

[keyboard-group]

The keyboard group specifies more automation for the application. The first number specifies the Key number, and the second number specifies the Group number. This section should be better described in the seq24-doc project on GitHub.

[extended-keys]

Additional keys (not yet represented in the Options dialog) to support additional keys for tempo-tapping, Seq32's new transport and connection functionality, and maybe a little more.

[New-keys]

Conditional support for reading Seq32 "rc" files.

[jack-transport]

This section covers various JACK settings, one setting per line. In order, the following numbers are specified:

```
- jack_transport - Enable sync with JACK Transport.
- jack_master - Seq24 will attempt to serve as JACK Master.
- jack_master_cond - Seq24 will fail to be Master if there is already a Master set.
- song_start_mode:
- 0 = Playback will be in Live mode. Use this to allow muting and unmuting of loops.
- 1 = Playback will use the Song Editor's data.
```

[midi-input]

This section covers the MIDI input busses, and has a format similar to "[midi-clock]". Generally, these busses are shown to the user with names such as "[1] seq24 1", and currently there is only one input buss. The first field is the port number, and the second number indicates whether it is disabled (0), or enabled (1).

[midi-clock-mod-ticks]

This section covers.... One common value is 64.

[manual-alsa-ports]

Set to 1 if you want seg24 to create its own ALSA ports and not connect to other clients.

[last-used-dir]

This section simply holds the last path-name that was used to read or write a MIDI file. We still need to add a check for a valid path, and currently the path must start with a "/", so it is not suitable for Windows.

[interaction-method]

This section specified the kind of mouse interaction.

- 0 = 'seq24' (original Seq24 method).
- 1 = 'fruity' (similar to a certain fruity sequencer we like).

The second data line is set to "1" if Mod4 can be used to keep seq24 in note-adding mode even after the right-click is released, and "0" otherwise.

Parameters

p Provides the performance object to which all of these options apply.

Returns

Returns true if the file was able to be opened for reading. Currently, there is no indication if the parsing actually succeeded.

Implements seq64::configfile.

12.48.3.2 write()

Parameters

p Provides a const reference to the main perform object. However, we have to cast away the constness, because too many of the perform getter functions are used in non-const contexts.

Returns

Returns true if the write operations all succeeded.

New boolean to show sequence numbers; ignored in legacy mode.

Implements seq64::configfile.

12.48.3.3 error_message()

Parameters

sectionname	Provides the name of the section for reporting the error.
-------------	---

Returns

Always returns false.

12.49 seq64::perfedit Class Reference

This class supports a Performance Editor that is used to arrange the patterns/sequences defined in the patterns panel.

Inheritance diagram for seq64::perfedit:

```
seq64::gui_window_gtk2
        - m_mainperf
        - m_window_x
       - m_window_y
- m_redraw_period_ms
        - m_is_realized
        + gui_window_gtk2()
+ ~gui_window_gtk2()
# perf()
        # quit()
        # redraw_period_ms()
# is_realized()
# scroll_hadjust()
# scroll_vadjust()
# scroll_haet()
# scroll_yaet()
        # scroll_vset()
# on_realize()
                   seq64::perfedit
 - m_peer_perfedit
- m_table
 - m_vadjust
- m_hadjust
 - m_vscroll
 - m_hscroll
- m_perfnames
- m_perfroll
 - m_perftime
 - m_menu_snap
and 32 more...
 + perfedit()
+ ~perfedit()
 + init_before_show()
+ enqueue_draw()
+ enregister_peer()
 + set_zoom()
+ get_toggle_jack()
+ toggle_jack()
+ rewind()
+ rewind()
+ fast_forward()
+ set_follow_transport()
+ toggle_follow_transport()
+ set_jack_mode()
+ set_transpose()
+ transpose_button_callback()
+ zoom_check()
- set_beat_width()
- set_baat_width()
- set_snap()
- set_beat_wid

- set_snap()

- set_guides()

- grow()

- set_looped()
 - expand()
- collapse()
- copy()
 - undo()
and 12 more..
```

Public Member Functions

- perfedit (perform &p., bool second_perfedit=false, int ppqn=SEQ64_USE_DEFAULT_PPQN)

 Principal constructor, has a reference to a perform object.
- virtual ~perfedit ()

This rote destructor does nothing.

void init_before_show ()

This function forwards its call to the perfroll function of the same name.

void enqueue_draw (bool forward=true)

Helper wrapper for calling perfroll::queue_draw() for one or both perfedits.

void enregister_peer (perfedit *peer)

Register the peer perfedit object.

void set_zoom (int z)

Implements the horizontal zoom feature.

bool get_toggle_jack ()

Gets the state fo the JACK toggle button in the Song editor, when compiled with seq32 JACK support.

void toggle_jack ()

Sets the state fo the JACK toggle button in the Song editor, when compiled with seq32 JACK support.

- · void rewind (bool press)
- void fast forward (bool press)
- void set_follow_transport ()

Sets the transport status when compiled for seq32 JACK support.

void toggle_follow_transport ()

Toggles the transport status when compiled for seq32 JACK support.

void set_jack_mode ()

Sets the JACK transport status, based on the status of the JACK button in the Song editor, when compiled for seq32 JACK support.

void set_transpose (int transpose)

Sets the value of transposition for this window.

void transpose_button_callback (int transpose)

The button callback for transposition for this window.

Static Public Member Functions

• static bool zoom check (int z)

Checks zoom values for the z/Z keystrokes used in perfroll and perftime.

Private Member Functions

void set_beats_per_bar (int bpm)

Sets the beats-per-measure text and value to the given value, and then calls set_guides().

void set_beat_width (int bw)

Sets the BW (beat width, or the denominator in the time signature) text and values to the given value, and then calls set_guides().

void set_snap (int snap)

Sets the snap text and values to the given value, and then calls set_guides().

· void set_guides ()

Sets the guides, which are the L and R user-interface elements.

• void grow ()

Increments the size of the perfroll and perftime objects.

void set_looped ()

Set the looping in the perform object.

· void expand ()

Implement the expand action.

· void collapse ()

Implement the collapse action.

• void copy ()

Implement the copy (actually, expand-and-copy) action.

• void undo ()

Implement the undo feature (Ctrl-Z).

• void redo ()

Implement the redo feature (Ctrl-R).

void popup_menu (Gtk::Menu *menu)

Opens the given popup menu.

• void draw_sequences ()

Forces a redraw of the sequences, though currently just the perfnames part of each sequence in the performance editor.

• bool timeout ()

Handles a drawing timeout.

void set_image (bool isrunning)

Changes the image used for the pause/play button.

void start_playing ()

Implement the playing.

• void pause_playing ()

Pauses the playing of the song, leaving the progress bar where it stopped.

void stop playing ()

Stop the playing.

void toggle_playing ()

Reverses the state of playback.

void on_realize ()

This callback function calls the base-class on_realize() function, and then connects the perfedit::timeout() function to the Glib signal-timeout, with a redraw timeout of redraw_period_ms().

• bool on_key_press_event (GdkEventKey *ev)

This function is the callback for a key-press event.

bool on_delete_event (GdkEventAny *)

All this callback function does is return false.

Private Attributes

perfedit * m_peer_perfedit

The partner instance of perfedit.

• Gtk::Table * m table

A whole horde of GUI elements.

Gtk::Adjustment * m_vadjust

Vertical adjust for piano roll.

• Gtk::Adjustment * m_hadjust

Horizontal adjust for piano roll.

• Gtk::VScrollbar * m vscroll

Vertical scroll for piano roll.

• Gtk::HScrollbar * m_hscroll

Horizonatl scroll for piano roll.

• perfnames * m_perfnames

Pattern names in leftmost column.

• perfroll * m_perfroll

The piano roll in the song editor.

• perftime * m_perftime

The time/measures bar above roll.

• Gtk::Menu * m_menu_snap The menu for grid-snap selection. Gtk::Menu * m menu xpose The menu for transpose selection. Gtk::Button * m_button_xpose Button to bring up transpose menu. • Gtk::Entry * m_entry_xpose Text edit for the transpose value. Gtk::Image * m_image_play The image for the play button. • Gtk::Button * m button snap Button to bring up the snap menu. Gtk::Entry * m_entry_snap Text edit for the grid-snap value. • Gtk::Button * m_button_stop The Stop Play button object. Gtk::Button * m_button_play Implements the yellow two-bar pause button. • Gtk::ToggleButton * m_button_loop Button for Left-to-Right looping. • Gtk::Button * m_button_expand Button for Left/Right expansion. • Gtk::Button * m button collapse Button for Left/Right collapse. • Gtk::Button * m_button_copy Expand and copy between L/R. Gtk::Button * m_button_grow Expand grid (bottom-right button). • Gtk::Button * m_button_undo Button to undo previous action. • Gtk::Button * m button redo Button to redo previous action. • Gtk::ToggleButton * m_button_jack Button to toggle JACK connection. Gtk::ToggleButton * m button follow Button to toggle JACK following. Gtk::Button * m button bpm Beats-per-measure menu button. Gtk::Entry * m_entry_bpm Text-edit for beats-per-measure. Gtk::Button * m button bw Beat-width menu button. • Gtk::Entry * m_entry_bw Text-edit for beat-width. • Gtk::HBox * m hbox Horizontal box (which?) in table. Gtk::HBox * m hlbox Horizontal box for buttons at top. Gtk::Tooltips * m tooltips

Container for tool-tips.

• Gtk::Menu * m_menu_bpm

Menus for time signature, beats per measure, beat width.

• Gtk::Menu * m_menu_bw

Drop-down menu for beat-width.

• int m_snap

Sets the horizontal grid snap-to in units of "pulses" or "ticks".

• int m_bpm

The current "beats per measure" value.

• int m bw

The current "beat width" value.

• int m_ppqn

The current "parts per quarter note" value.

• bool m_is_running

Holds the current status of running, for use in display the play versus pause icon.

• int m standard bpm

The standard "beats per measure" of Sequencer64, which here matches the beats-per-measure displayed in the perfroll (piano roll).

Friends

void update_perfedit_sequences ()

This global function in the seq64 namespace calls perfedit :: draw_sequences(), if the global perfedit objects exist.

int FF RW timeout (void *arg)

This global function in the seq64 namespace is passed to the gtk_timeout callback.

Additional Inherited Members

12.49.1 Detailed Description

It has a segroll and piano roll? No, it has a perform, a perfnames, a perfroll, and a perftime.

12.49.2 Constructor & Destructor Documentation

12.49.2.1 perfedit()

We've reordered the pointer members and put them in the initializer list to make the constructor a bit cleaner.

Todo Offload most of the work into an initialization function like options does.

Parameters

р	Refers to the main performance object.
second_perfedit	If true, this object is the second perfedit object.
ppqn	The optionally-changed PPQN value to use for the performance editor.

Generated by Doxygen

12.49.2.2 ∼perfedit()

```
virtual seq64::perfedit::~perfedit ( ) [inline], [virtual]
```

We're going to have to run the application through valgrind to make sure that nothing is left behind.

12.49.3 Member Function Documentation

```
12.49.3.1 init_before_show()
void seq64::perfedit::init_before_show ( )
```

It does not seem to need to also forward to the perftime function of the same name.

12.49.3.2 enqueue_draw()

Note that we call the children's queue_draw() functions, not enqueue_draw(), otherwise we'll get stack overflow.

Parameters

forward

If true (the default), pass the call to the peer. When passing this call to the peer, this parameter is set to false to prevent an infinite loop and the resultant stack overflow.

12.49.3.3 zoom_check()

It has to range from greater than 1 (the highest zoom-in causes an unexplained drawing artifact at this time), and not greater than four times the c_perf_scale_x value, at which point we have zoomed out so far that the measure numbers are almost completely obscured.

Parameters

z The desired zoom value to validate.

12.49.3.4 enregister_peer()

This function is meant to be called by mainwind, which creates the perfedits and then makes sure they get along. Only the first call to this function will work; only one peer can be registered.

peer The peer perfedit object to register, if not null.

```
12.49.3.5 set_zoom()
```

```
void seq64::perfedit::set_zoom ( int \ z \ )
```

Parameters

z The zoom value to be set. The child zoom functions called each check that this value is valid.

12.49.3.6 get_toggle_jack()

```
bool seq64::perfedit::get_toggle_jack ( )
```

Returns

Returns the JACK button's get_active() status.

12.49.3.7 toggle_jack()

```
void seq64::perfedit::toggle_jack ( )
```

Note that this will trigger the button signal callback.

12.49.3.8 rewind()

12.49.3.9 fast_forward()

12.49.3.10 set_follow_transport()

```
void seq64::perfedit::set_follow_transport ( )
```

Note that this will trigger the button signal callback.

12.49.3.11 toggle_follow_transport()

```
void seq64::perfedit::toggle_follow_transport ( )
```

Note that this will trigger the button signal callback.

12.49.3.12 set_jack_mode()

```
void seq64::perfedit::set_jack_mode ( )
```

To avoid a lot of pointer dereferencing, much of the code is offloaded to perform::set_jack_mode(), which now returns a boolean.

12.49.3.13 set_transpose()

Parameters

transpose

The amount to transpose the transposable sequences. We need to add validation at some point, if the widget does not enforce that.

12.49.3.14 transpose_button_callback()

Parameters

transpose The amount to transpose the transposable sequences.

12.49.3.15 set_beats_per_bar()

```
void seq64::perfedit::set_beats_per_bar (
    int bpm ) [private]
```

The usage of is modified was faulty. Offloaded it to the perform object to make it more foolproof. See the perform ::modify() function.

Parameters

bpm Provides the beats/measure or beats/bar value to be set. This value is basically the numerator of the time signature.

```
12.49.3.16 set_beat_width()
```

The usage of is modified was faulty. Offloaded it to the perform object to make it more foolproof. See the perform ::modify() function.

Parameters

bw

Provides the beat width to be set. The beat width is basically the denominator of the time signature.

12.49.3.17 set_snap()

Parameters

snap

Provide the snap value to be set. This value is basically the numerator of the expression "1 / snap".

12.49.3.18 set_guides()

```
void seq64::perfedit::set_guides ( ) [private]
```

See the set_snap() function.

It's a little confusing; I assigned the label "m_standard_bpm" to the value 4 in "measure_pulse = $192 * 4 * m_bpm / m_bw$ ", but I am not sure I understand this equation... why the extra factor of 4? That 4 appears in "c_ppqn * 4" a lot in the original code.

12.49.3.19 grow()

```
void seq64::perfedit::grow ( ) [private]
```

Make sure that setting the modified flag makes sense for this operation. It doesn't seem to modify members.

12.49.3.20 set_looped()

```
void seq64::perfedit::set_looped ( ) [private]
```

12.49.3.21 expand()

```
void seq64::perfedit::expand ( ) [private]
```

This action opens up a space of events between the L and R (left and right) markers. This action is preceded by pushing an Undo operation in the perform object, moving its triggers, and telling the perfroll to redraw.

12.49.3.22 collapse()

```
void seq64::perfedit::collapse ( ) [private]
```

This action removes all events between the L and R (left and right) markers. This action is preceded by pushing an Undo operation in the perform object, not moving its triggers (they go away), and telling the perfoll to redraw.

12.49.3.23 copy()

```
void seq64::perfedit::copy ( ) [private]
```

This action opens up a space of events between the L and R (left and right) markers, and copies the information from the same amount of events that follow the R marker. This action is preceded by pushing an Undo operation in the perform object, copying its triggers, and telling the perfroll to redraw.

12.49.3.24 undo()

```
void seq64::perfedit::undo ( ) [private]
```

We pop an Undo trigger, and then ask the perfroll to queue up a (re)drawing action.

12.49.3.25 redo()

```
void seq64::perfedit::redo ( ) [private]
```

We pop an Redo trigger, and then ask the perfroll to queue up a (re)drawing action.

12.49.3.26 popup_menu()

12.49.3.27 draw_sequences()

```
void seq64::perfedit::draw_sequences ( ) [private]
```

This is meant to be called when the focus of an open seqedit or eventedit window changes.

12.49.3.28 timeout()

```
bool seq64::perfedit::timeout ( ) [private]
```

It redraws "dirty" sequences in the perfroll and the perfnames objects, and shows draw progress on the perfroll. It also changes the pause/play image if the status of running has changed. This function is called frequently and continuously. It will work for both perfedit windows, if both are up.

12.49.3.29 set_image()

isrunnina	If true, the image should be the pause image. Otherwise, it should be the play image.
	in the state and go and a state passes and got of the state of the play in age.

12.49.3.30 start_playing()

```
void seq64::perfedit::start_playing ( ) [private]
```

JACK will be used if it is present and, in the application, enabled and working. Note the new flag to let perform know that it is a pause/play request from the perfedit window. In other words, a forced Song mode.

12.49.3.31 pause_playing()

```
void seq64::perfedit::pause_playing ( ) [private]
```

Keeps the stop button enabled as a kind of rewind for ALSA. Stop in place!

12.49.3.32 stop_playing()

```
void seq64::perfedit::stop_playing ( ) [private]
```

We need to make the progress line move back to the beginning right away here.

12.49.3.33 toggle_playing()

```
void seq64::perfedit::toggle_playing ( ) [inline], [private]
```

Meant only to be called when the "Play" button is pressed. Currently, the GUI does not change. This function will ultimately act like a Pause/Play button, but currently the pause functionality on works (partially) for JACK transport. Currently not used.

12.49.3.34 on_realize()

```
void seq64::perfedit::on_realize ( ) [private]
```

12.49.3.35 on_key_press_event()

```
bool seq64::perfedit::on_key_press_event ( {\tt GdkEventKey} \ * \ ev \ ) \quad [private]
```

By default, the space-bar starts the playing, and the Escape key stops the playing. The start/end key may be the same key (i.e. space-bar), allow toggling when the same key is mapped to both triggers. Note that we now pass false in the call to perform::playback_key_event(), if SEQ64_PAUSE_SUPPORT is compiled in. Song mode doesn't yield the pause effect we want.

ev Provides the key event to implement.

12.49.3.36 on_delete_event()

12.49.4 Friends And Related Function Documentation

12.49.4.1 update_perfedit_sequences

```
void update_perfedit_sequences ( ) [friend]
```

It is used by other objects (seqedit and eventedit) that can modify the currently-edited sequence shown in the perfedit (song window).

12.49.4.2 FF_RW_timeout

```
int FF_RW_timeout ( \mbox{void} \ * \ arg \ ) \ \ [\mbox{friend}]
```

Parameters

arg Provide a putative pointer to the perform object.

Returns

Returns the value of the perform::FF_RW_timeout() call if Seq32 transport support is enabled and the arg parameter is good, otherwise false is returned.

12.49.5 Field Documentation

12.49.5.1 m_peer_perfedit

```
perfedit* seq64::perfedit::m_peer_perfedit [private]
```

12.49.5.2 m_table

```
Gtk::Table* seq64::perfedit::m_table [private]
```

Layout table for song editor.

```
12.49.5.3 m_vadjust
Gtk::Adjustment* seq64::perfedit::m_vadjust [private]
12.49.5.4 m_hadjust
Gtk::Adjustment* seq64::perfedit::m_hadjust [private]
12.49.5.5 m_vscroll
Gtk::VScrollbar* seq64::perfedit::m_vscroll [private]
12.49.5.6 m_hscroll
Gtk::HScrollbar* seq64::perfedit::m_hscroll [private]
12.49.5.7 m_perfnames
perfnames* seq64::perfedit::m_perfnames [private]
12.49.5.8 m_perfroll
perfrol1* seq64::perfedit::m_perfroll [private]
12.49.5.9 m_perftime
perftime* seq64::perfedit::m_perftime [private]
12.49.5.10 m_menu_snap
Gtk::Menu* seq64::perfedit::m_menu_snap [private]
12.49.5.11 m_menu_xpose
Gtk::Menu* seq64::perfedit::m_menu_xpose [private]
12.49.5.12 m_button_xpose
Gtk::Button* seq64::perfedit::m_button_xpose [private]
```

```
12.49.5.13 m_entry_xpose
Gtk::Entry* seq64::perfedit::m_entry_xpose [private]
12.49.5.14 m_image_play
Gtk::Image* seq64::perfedit::m_image_play [private]
12.49.5.15 m button snap
Gtk::Button* seq64::perfedit::m_button_snap [private]
12.49.5.16 m_entry_snap
Gtk::Entry* seq64::perfedit::m_entry_snap [private]
12.49.5.17 m_button_stop
Gtk::Button* seq64::perfedit::m_button_stop [private]
12.49.5.18 m_button_play
Gtk::Button* seq64::perfedit::m_button_play [private]
The Play button object.
12.49.5.19 m_button_loop
Gtk::ToggleButton* seq64::perfedit::m_button_loop [private]
12.49.5.20 m_button_expand
Gtk::Button* seq64::perfedit::m_button_expand [private]
12.49.5.21 m_button_collapse
Gtk::Button* seq64::perfedit::m_button_collapse [private]
12.49.5.22 m_button_copy
Gtk::Button* seq64::perfedit::m_button_copy [private]
```

```
12.49.5.23 m_button_grow
Gtk::Button* seq64::perfedit::m_button_grow [private]
12.49.5.24 m_button_undo
Gtk::Button* seq64::perfedit::m_button_undo [private]
12.49.5.25 m_button_redo
Gtk::Button* seq64::perfedit::m_button_redo [private]
12.49.5.26 m_button_jack
Gtk::ToggleButton* seq64::perfedit::m_button_jack [private]
12.49.5.27 m_button_follow
Gtk::ToggleButton* seq64::perfedit::m_button_follow [private]
12.49.5.28 m_button_bpm
Gtk::Button* seq64::perfedit::m_button_bpm [private]
12.49.5.29 m_entry_bpm
Gtk::Entry* seq64::perfedit::m_entry_bpm [private]
12.49.5.30 m_button_bw
Gtk::Button* seq64::perfedit::m_button_bw [private]
12.49.5.31 m_entry_bw
Gtk::Entry* seq64::perfedit::m_entry_bw [private]
12.49.5.32 m_hbox
Gtk::HBox* seq64::perfedit::m_hbox [private]
```

```
12.49.5.33 m_hlbox
Gtk::HBox* seq64::perfedit::m_hlbox [private]
12.49.5.34 m_tooltips
Gtk::Tooltips* seq64::perfedit::m_tooltips [private]
12.49.5.35 m_menu_bpm
Gtk::Menu* seq64::perfedit::m_menu_bpm [private]
Drop-down menu for beats/minute.
12.49.5.36 m_menu_bw
Gtk::Menu* seq64::perfedit::m_menu_bw [private]
12.49.5.37 m_snap
int seq64::perfedit::m_snap [private]
12.49.5.38 m_bpm
int seq64::perfedit::m_bpm [private]
Do not confuse it with BPM (beats per minute). The numerator of the time signature.
12.49.5.39 m bw
int seq64::perfedit::m_bw [private]
The denominator of the time signature.
12.49.5.40 m_ppqn
int seq64::perfedit::m_ppqn [private]
12.49.5.41 m_is_running
```

bool seq64::perfedit::m_is_running [private]


12.49.5.42 m_standard_bpm

```
int seq64::perfedit::m_standard_bpm [private]
```

12.50 seq64::perfnames Class Reference

This class implements the left-side keyboard in the patterns window.

Inheritance diagram for seq64::perfnames:



Public Member Functions

perfnames (perform &p, perfedit &parent, Gtk::Adjustment &vadjust)

Principal constructor for this user-interface object.

virtual ∼perfnames ()

Let's provide a do-nothing virtual destructor.

• void redraw_dirty_sequences ()

Redraws sequences that have been modified.

Private Member Functions

void enqueue_draw ()

Wraps queue_draw() and forwards the call to the parent perfedit, so that it can forward it to any other perfedit that exists, and to the other sub-elements of the song editor.

int convert_y (int y)

Converts a y-value into a sequence number and returns it.

void draw sequences ()

New function to encapsulate forced redrawing of all sequence names in the current viewport.

void draw_sequence (int sequence)

Draw the given sequence.

· void change_vert ()

Change the vertial offset of a sequence/pattern.

· void redraw (int sequence)

Redraw the given sequence.

void on_realize ()

Handles the callback when the window is realized.

• bool on_expose_event (GdkEventExpose *ev)

Handles an on-expose event.

• bool on button press event (GdkEventButton *ev)

Provides the callback for a button press, and it handles only a left mouse button [the right mouse button is handled in on_button_release_event()].

bool on_button_release_event (GdkEventButton *ev)

Handles a button-release for the right button, bringing up a popup menu that is identical to the right-click popup menu for a slot in the patterns panel (mainwid), and context sensitive.

void on_size_allocate (Gtk::Allocation &)

Handles a size-allocation event.

bool on_scroll_event (GdkEventScroll *ev)

Handle the vertical scrolling of the window.

Private Attributes

· perfedit & m_parent

Provides a link to the perfedit that created this object.

· int m names chars

Provides the number of the characters in the name box.

int m_char_w

Provides the "real" width of a character.

· int m setbox w

Provides the width of the "set number" box.

int m_namebox_w

Provides the width of the "name" box.

• int m_names_x

Provides the width of the names box, which is the width of a character for 24 characters.

· int m_names_y

Provides the height of the names box, which is hardwired to 24 pixels.

· int m_xy_offset

Provides the horizontal and vertical offsets of the text relative to the names box.

· const int m seqs in set

The number of sequences in a set, currently still hardwired to 32.

• const int m_sequence_max

The maximum number of sequences, current $32 \times 32 = 1024$.

• int m_sequence_offset

The offset from the 0th sequence, which is determined by the vertical view of the piano roll, controlled by the vertical scroll-bar.

• bool m sequence active [c max sequence]

Indicates if the given sequence is active or not.

Friends

· class perfedit

Additional Inherited Members

12.50.1 Detailed Description

It inherits from gui_drawingarea_gtk2 to support the font, color, and other GUI functionality, and from seqmenu to support the right-click Edit/New/Cut right-click menu.

Obsolete Note the usage of virtual base classes. Since these can add some extra overhead, we should determine if we can do without the virtuality (and indeed it doesn't seem to be needed).

12.50.2 Constructor & Destructor Documentation

12.50.2.1 perfnames()

Weird is that the window (x,y) are set to (c_names_x, 100), when c_names_y is 22 (now 24) in globals.h.

Parameters

р	Provides a reference to the main performance object of the application.
parent	Provides a reference to the object that contains this object, so that this object can tell the parent to queue up a drawing operation.
vadjust	Provides the vertical scrollbar object needed so that perfnames can respond to scrollbar cursor/thumb movement.

12.50.2.2 \sim perfnames()

```
virtual seq64::perfnames::~perfnames ( ) [inline], [virtual]
```

12.50.3 Member Function Documentation

12.50.3.1 redraw_dirty_sequences()

```
void seq64::perfnames::redraw_dirty_sequences ( )
```

12.50.3.2 enqueue_draw()

```
void seq64::perfnames::enqueue_draw ( ) [private]
```

The parent perfedit will call perfnames::queue_draw() on behalf of this object, and it will pass a perfnames.::enqueue_draw() to the peer perfedit's perfnames, if the peer exists.

12.50.3.3 convert_y()

Used in figuring out which sequence to mute/unmute in the performance editor.

Parameters

y The y value (within the vertical limits of the perfnames column to the left of the performance editor's piano roll.

Returns

Returns the sequence number corresponding to the y value.

12.50.3.4 draw_sequences()

```
void seq64::perfnames::draw_sequences ( ) [private]
```

12.50.3.5 draw_sequence()

This function has to be prepared to handle an almost endless list of sequences, including unused ones, to draw them all with compatible styles. The sequences are grouped by set-number. The set-number occurs every 32 sequences in the leftmost column of the window.

- 1. Render the set number, or a blank box, in leftmost column. If the y height of the first draw_rectangle is m_names_y + 1, then we get a black line for the blank tracks, looks ugly.
- 2. Make sure that the rectangle drawn with the proper background colors for various combinations of muting and highlighting, otherwise just the name is properly colored.
- 3. Render the column with the name of the sequence. The channel number ranges from 1 to 16, but SMF 0 is indicated on-screen by a channel number of 0. We get the label format from the perform object, for consistency across windows.

seqnum Index to the sequence information to be drawn.

12.50.3.6 change_vert()

```
void seq64::perfnames::change_vert ( ) [private]

12.50.3.7 redraw()
```

This function is a virtual function of segmenu that must be overridden in this class.

int sequence) [inline], [private], [virtual]

Parameters

sequence Provides the number of the sequence to be redra	wn.
--	-----

Implements seq64::seqmenu.

void seq64::perfnames::redraw (

12.50.3.8 on_realize()

```
void seq64::perfnames::on_realize ( ) [private]
```

It first calls the base-class version of on_realize(). Then it allocates any additional resources needed.

12.50.3.9 on_expose_event()

It draws all of the sequences that will be visible.

We could actually optimize this a tiny bit, to save some additions in the for loop.

ev The expose event, not used.

Returns

Always returns true.

12.50.3.10 on_button_press_event()

```
bool seq64::perfnames::on_button_press_event (
    GdkEventButton * ev ) [private]
```

Two operations are supported by left-clicking on the sequence/track name:

- Normal. Toggles the mute status of the sequence that is clicked.
- Shift. Toggles the mutes status of all other sequences, making this operation an easy way to preview a single sequence in the performance editor, then bring back the rest of the tracks.

Parameters

ev The mouse button event.

Returns

Always returns true.

12.50.3.11 on_button_release_event()

Parameters

p0 The button event.

Returns

Always returns false.

12.50.3.12 on_size_allocate()

It first calls the base-class version of this function.

а

The allocation event. It is passed to the base-class on_size_allocate() function, and then m_window_x and m_window_y are set to the width and height, respectively, of the allocation.

12.50.3.13 on_scroll_event()

The vertical value is incremented or decremented by the amount of the step increment, and the page is clamped to the new value.

Parameters

ev The scrolling event.

Returns

Always returns true.

12.50.4 Friends And Related Function Documentation

12.50.4.1 perfedit

```
friend class perfedit [friend]
```

12.50.5 Field Documentation

12.50.5.1 m_parent

```
perfedit& seq64::perfnames::m_parent [private]
```

We want to support two perfedit windows, but the children of perfedit will have to communicate changes requiring a redraw through the parent.

```
12.50.5.2 m_names_chars
```

```
int seq64::perfnames::m_names_chars [private]
```

Pretty much hardwired to 24 at present.

```
12.50.5.3 m_char_w
```

```
int seq64::perfnames::m_char_w [private]
```

This value is obtained from a font-renderer accessor function.

```
12.50.5.4 m_setbox_w
int seq64::perfnames::m_setbox_w [private]
This used to be hardwired to 6 * 2 (character-width times two).
12.50.5.5 m_namebox_w
int seq64::perfnames::m_namebox_w [private]
This used to be a weird calculation based on character width.
12.50.5.6 m_names_x
int seq64::perfnames::m_names_x [private]
12.50.5.7 m_names_y
int seq64::perfnames::m_names_y [private]
This value was once 22 pixels, but we need a little extra room for our new font. This extra room is compatible enough
with the old font, as well.
12.50.5.8 m_xy_offset
int seq64::perfnames::m_xy_offset [private]
Currently hardwired.
12.50.5.9 m_seqs_in_set
const int seq64::perfnames::m_seqs_in_set [private]
12.50.5.10 m_sequence_max
const int seq64::perfnames::m_sequence_max [private]
12.50.5.11 m_sequence_offset
```

int seq64::perfnames::m_sequence_offset [private]

```
12.50.5.12 m_sequence_active
```

```
bool seq64::perfnames::m_sequence_active[c_max_sequence] [private]
```

If this really is the true meaning of this value, we ought to get it directly from the sequence if we can.

12.51 seq64::perform Class Reference

This class supports the performance mode.

Public Types

```
enum mute_op_t {
    MUTE_TOGGLE,
    MUTE_OFF,
    MUTE_ON }
    Provides settings for muting.
enum ff_rw_button_t {
    FF_RW_REWIND,
    FF_RW_FORWARD }
```

Provides setting for the fast-forward and rewind functionality.

Public Member Functions

• perform (gui_assistant &mygui, int ppqn=SEQ64_USE_DEFAULT_PPQN)

This construction initializes a vast number of member variables, some of them public (but we're working on that)!

∼perform ()

The destructor sets some running flags to false, signals this condition, then joins the input and output threads if the were launched.

• bool is_modified () const

'Getter' function for member m_is_modfied

void modify ()

'Setter' function for member m_is_modified This setter only sets the modified-flag to true.

· int sequence_count () const

'Getter' function for member m_sequence_count It is better to call this getter before bothering to even try to use a sequence.

• int sequence_max () const

'Getter' function for member m_sequence_max

bool is_control_status () const

'Getter' function for member m_control_status

• void set_edit_sequence (int seqnum)

'Setter' function for member m_edit_sequence

void unset_edit_sequence (int seqnum)

 ${\it 'Setter' function for member m_edit_sequence}$

bool is_edit_sequence (int seqnum) const

'Getter' function for member m_edit_sequence

• int get_beats_per_bar () const

'Getter' function for member m_beats_per_bar

void set_beats_per_bar (int bpm)

'Setter' function for member m_beats_per_bar

int get_beat_width () const

'Getter' function for member m_beat_width

void set_beat_width (int bw)

'Setter' function for member m_beat_width

void clocks_per_metronome (int cpm)

'Setter' function for member m_clocks_per_metronome

int clocks_per_metronome () const

'Getter' function for member m_clocks_per_metronome

void set_32nds_per_quarter (int tpq)

'Setter' function for member m_32nds_per_quarter

• int get_32nds_per_quarter () const

'Getter' function for member m_32nds_per_quarter

void us_per_quarter_note (long upqn)

'Setter' function for member m_us_per_quarter_note

• long us_per_quarter_note () const

'Getter' function for member m_us_per_quarter_note

const gui_assistant & gui () const

'Getter' function for member m_gui_support The const getter.

• gui_assistant & gui ()

'Getter' function for member m gui support The un-const getter.

const keys_perform & keys () const

'Getter' function for member m_gui_support.keys() The const getter.

keys_perform & keys ()

'Getter' function for member m_gui_support.keys() The un-const getter.

mastermidibus & master_bus ()

'Getter' function for member m_master_bus

void filter_by_channel (bool flag)

'Setter' function for member m_master_bus.filter_by_channel()

bool is_running () const

'Getter' function for member m_running Could also be called "is_playing()".

bool is_pattern_playing () const

'Setter' function for member m_is_pattern_playing

bool toggle_song_start_mode ()

'Setter' function for member m_song_start_mode

void song_start_mode (bool flag)

'Setter' function for member m_song_start_mode

bool song_start_mode () const

'Getter' function for member m_song_start_mode

• bool is_jack_running () const

'Getter' function for member m_jack_asst.is_running() This function is useful for announcing the status of JACK in user-interface items that only have access to the perform object.

• bool is_jack_master () const

'Getter' function for member m_jack_asst.is_master() Also now includes is_jack_running(), since one cannot be JACK Master if JACK is not running.

void enregister (performcallback *pfcb)

Adds a pointer to an object to be notified by this perform object.

- void toggle_jack_mode ()
- bool set_jack_mode (bool mode)

Encapsulates behavior needed by perfedit.

bool get_toggle_jack () const

'Getter' function for member m_jack_asst.get_jack_mode()

void set_jack_stop_tick (midipulse tick)

'Setter' function for member m_jack_asst.set_jack_stop_tick()

unsigned short combine_bytes (midibyte b0, midibyte b1)

Combines bytes into an unsigned-short value.

- void FF rewind ()
- bool FF RW timeout ()

Convenience function.

void start_from_perfedit (bool flag)

'Setter' function for member m_start_from_perfedit

bool start_from_perfedit () const

'Getter' function for member m_start_from_perfedit

void set_follow_transport (bool flag)

'Getter' function for member m_jack_asst.set_follow_transport()

• bool get_follow_transport () const

'Getter' function for member m_jack_asst.get_follow_transport()

void toggle_follow_transport ()

'Setter' function for member m_jack_asst.toggle_follow_transport()

void set_reposition (bool postype=true)

'Getter' function for member m_reposition

• ff_rw_button_t ff_rw_type ()

'Getter' function for member m_FF_RW_button_type

void ff_rw_type (ff_rw_button_t button_type)

'Getter' function for member m_FF_RW_button_type

void rewind (bool press)

Sets the rewind status.

· void fast_forward (bool press)

Sets the fast-forward status.

void reposition (midipulse tick)

Encapsulates some repositioning code needed to move the position to the mouse pointer location in perfroll.

• bool clear all ()

Clears all of the patterns/sequences.

void launch (int ppqn)

Calls the MIDI buss and JACK initialization functions and the input/output thread-launching functions.

void new_sequence (int seq)

Creates a new pattern/sequence for the given slot, and sets the new pattern's master MIDI bus address.

void add_sequence (sequence *seq, int perf)

Adds a pattern/sequence pointer to the list of patterns.

void delete_sequence (int seq)

Deletes a pattern/sequence by number.

• bool is sequence in edit (int seq)

Check if the pattern/sequence, given by number, has an edit in progress.

void clear_sequence_triggers (int seq)

Clears the patterns/sequence for the given sequence, if it is active.

void print_triggers () const

Shows all the triggers of all the sequences.

· void finish ()

The rough opposite of launch(); it doesn't stop the threads.

midipulse get_tick () const

'Getter' function for member m_tick

• midipulse get_jack_tick () const

'Getter' function for member m_jack_tick

void set_jack_tick (midipulse tick)

'Setter' function for member m_jack_tick

void set_left_tick (midipulse tick, bool setstart=true)

Set the left marker at the given tick.

• midipulse get_left_tick () const

'Getter' function for member m_left_tick

void set_start_tick (midipulse tick)

'Setter' function for member m_starting_tick

• midipulse get_start_tick () const

'Setter' function for member m_starting_tick

void set_right_tick (midipulse tick, bool setstart=true)

Set the right marker at the given tick.

• midipulse get_right_tick () const

'Getter' function for member m_right_tick

• double left_right_size () const

Convenience function for JACK support when loop in song mode.

bool is_active (int seq) const

Checks the pattern/sequence for activity.

void apply_song_transpose ()

Calls the apply song transpose() function for all active sequences.

void set_transpose (int t)

'Setter' function for member m_transpose For sanity's sake, the values are restricted to +-64.

• int get_transpose () const

'Getter' function for member m_transpose

int get_beats_per_minute ()

'Getter' function for member m_master_bus.get_beats_per_minute Retrieves the BPM setting of the master MIDI buss

void set sequence control status (int status)

If the given status is present in the c_status_snapshot, the playing state is saved.

void unset_sequence_control_status (int status)

If the given status is present in the c_status_snapshot, the playing state is restored.

void sequence_playing_toggle (int seq)

If the given sequence is active, then it is toggled.

void sequence_playing_change (int seq, bool on)

Turn the playing of a sequence on or off, if it is active.

· void sequence_playing_on (int seq)

Calls sequence_playing_change() with a value of true.

void sequence_playing_off (int seq)

Calls sequence_playing_change() with a value of false.

void mute_all_tracks (bool flag=true)

Mutes/unmutes all tracks in the current set of active patterns/sequences.

• void toggle_all_tracks ()

Toggles the mutes status of all tracks in the current set of active patterns/sequences.

• bool armed_saved () const

'Getter' function for member m_armed_saved

- void toggle_playing_tracks ()
- void mute screenset (int ss, bool flag=true)

Mutes/unmutes all tracks in the desired screen-set.

void output_func ()

Performance output function.

void input_func ()

This function is called by input thread func().

void set_group_mute_state (int gtrack, bool muted)

This function sets the mute state of an element in the m_mute_group array.

bool get_group_mute_state (int gtrack)

The opposite of set_group_mute_state(), it gets the value of the desired track.

· void set offset (int offset)

Calculates the offset into the screen sets.

• int get_offset () const

'Getter' function for member m offset

void save_playing_state ()

For all active patterns/sequences, this function gets the playing status and saves it in m_sequence_state[i].

void restore_playing_state ()

For all active patterns/sequences, this function gets the playing status from m_sequence_state[i] and sets it for the sequence.

std::string key_name (unsigned int k) const

Here follows a few forwarding functions for the keys_perform-derived classes.

keys_perform::SlotMap & get_key_events ()

Forwarding function for key events.

• keys_perform::SlotMap & get_key_groups ()

Forwarding function for key groups.

keys_perform::RevSlotMap & get_key_events_rev ()

Forwarding function for reverse key events.

keys_perform::RevSlotMap & get_key_groups_rev ()

Forwarding function for reverse key groups.

· bool show ui sequence key () const

'Getter' function for member m_show_ui_sequency_key Provides access to keys().show_ui_sequence_key().

• void show_ui_sequence_key (bool flag)

'Setter' function for member m show ui sequency key

• bool show ui sequence number () const

'Getter' function for member m_show_ui_sequency_number Provides access to keys().show_ui_sequence_number().

• void show_ui_sequence_number (bool flag)

'Getter' function for member m_show_ui_sequency_number

unsigned int lookup keyevent key (int segnum)

Gets the event key for the given sequence.

long lookup_keyevent_seq (unsigned int keycode)

Gets the sequence number for the given event key.

unsigned int lookup_keygroup_key (long groupnum)

Gets the group key for the given sequence.

• long lookup_keygroup_group (unsigned int keycode)

Gets the group number for the given group key.

void start_playing (bool songmode=false)

Encapsulates a series of calls used in mainwnd.

void pause playing (bool songmode=false)

Pause playback, so that progress bars stay where they are, and playback always resumes where it left off, even in ALSA mode.

void stop playing ()

Encapsulates a series of calls used in mainwnd.

• void start key (bool songmode=false)

Invoke the start key functionality.

void pause_key (bool songmode=false)

Invoke the pause key functionality.

void stop_key ()

Invoke the stop key functionality.

void learn_toggle ()

Encapsulates some calls used in mainwnd.

int decrement_beats_per_minute ()

Encapsulates some calls used in mainwnd.

int increment_beats_per_minute ()

Encapsulates some calls used in mainwnd.

int decrement_screenset ()

Encapsulates some calls used in mainwnd.

int increment_screenset ()

Encapsulates some calls used in mainwnd.

bool highlight (const sequence &seq) const

True if a sequence is empty and should be highlighted.

• bool is_smf_0 (const sequence &seq) const

True if the sequence is an SMF 0 sequence.

const sequence * get_sequence (int seq) const

Retrieves the actual sequence, based on the pattern/sequence number.

sequence * get_sequence (int seq)

Retrieves the actual sequence, based on the pattern/sequence number.

void sequence_key (int seq)

Handle a sequence key to toggle the playing of an active pattern in the selected screen-set.

std::string sequence_label (const sequence &seq)

Provides a way to format the sequence parameters string for display in the mainwid or perfnames modules.

void set_input_bus (int bus, bool input_active)

Sets the input bus, and handles the special "key labels on sequence" and "sequence numbers on sequence" functionality.

• bool mainwnd_key_event (const keystroke &k)

Provided for mainwnd :: on_key_press_event() and mainwnd :: on_key_release_event() to call.

bool perfroll_key_event (const keystroke &k, int drop_sequence)

Provided for perfroll :: on_key_press_event() and perfroll :: on_key_release_event() to call.

• bool playback_key_event (const keystroke &k, bool songmode=false)

New function provided to unify the stop/start (space/escape) behavior of the various windows where playback can be started, paused, or stopped.

• void move triggers (bool direction)

If the left tick is less than the right tick, then, for each sequence that is active, its triggers are moved by the difference between the right and left in the specified direction.

void copy triggers ()

If the left tick is less than the right tick, then, for each sequence that is active, its triggers are copied, offset by the difference between the right and left.

void push_trigger_undo (int track=SEQ64_ALL_TRACKS)

For every active sequence, call that sequence's push_trigger_undo() function.

void pop_trigger_undo ()

For every active sequence, call that sequence's pop_trigger_undo() function.

- void pop_trigger_redo ()
- bool is_dirty_main (int seq)

Checks the pattern/sequence for main-dirtiness.

• bool is_dirty_edit (int seq)

Checks the pattern/sequence for edit-dirtiness.

bool is_dirty_perf (int seq)

Checks the pattern/sequence for perf-dirtiness.

· bool is_dirty_names (int seq)

Checks the pattern/sequence for names-dirtiness.

bool is_exportable (int seq) const

Indicates that the desired sequence is active, unmuted, and has a non-zero trigger count.

void set_screenset (int ss)

Sets the m_screenset value (the index or ID of the current screen set).

• int get_screenset () const

'Getter' function for member m_screenset

• int get_playing_screenset () const

'Getter' function for member m_playing_screen

Private Member Functions

· bool have_undo () const

'Getter' function for member m_have_undo

void set have undo (bool undo)

'Setter' function for member m_have_undo Note that, if the undo parameter is true, then we mark the performance as modified.

bool have_redo () const

'Getter' function for member m_have_redo

void set_have_redo (bool redo)

'Setter' function for member m_have_redo

void split_trigger (int seqnum, midipulse tick)

Convenience function for perfroll's split-trigger functionality.

midipulse get_max_trigger ()

Locates the largest trigger value among the active sequences.

void collapse ()

Convenience function for perfedit's collapse functionality.

• void copy ()

Convenience function for perfedit's copy functionality.

· void expand ()

Convenience function for perfedit's expand functionality.

• midi_control & midi_control_toggle (int seq)

Retrieves a reference to a value from m_midi_cc_toggle[].

midi_control & midi_control_on (int seq)

Retrieves a reference to a value from m_midi_cc_on[].

• midi_control & midi_control_off (int seq)

Retrieves a reference to a value from m_midi_cc_off[].

• void handle_midi_control (int control, bool state)

Handle the MIDI Control values that provide some automation for the application.

• const std::string & get_screen_set_notepad (int screen_set) const

Retrieves the given string from m_screen_set_notepad[].

const std::string & current_screen_set_notepad () const

Returns the notepad text for the current screen-set.

void set screen set notepad (int screenset, const std::string ¬e)

Copies the given string into m_screen_set_notepad[].

void set_screen_set_notepad (const std::string ¬e)

Sets the notepad text for the current screen-set.

void set_playing_screenset ()

Sets the screen set that is active, based on the value of m_screenset.

· bool any group unmutes () const

'Getter' function for member m_mute_group[]

void mute_group_tracks ()

If m_mode_group is true, then this function operates.

void select_and_mute_group (int g_group)

Select a mute group and then mutes the track in the group.

void set_song_mute (mute_op_t op)

Provides for various settings of the song-mute status of all sequences in the song.

void set_mode_group_mute ()

'Setter' function for member m_mode_group

void unset_mode_group_mute ()

'Setter' function for member m_mode_group Unsets this member.

void select_group_mute (int g_mute)

If we're in group-learn mode, then this function gets the playing statuses of all of the sequences in the current playscreen, and copies them into the desired mute-group.

void set_mode_group_learn ()

Sets the group-mute mode, then the group-learn mode, then notifies all of the notification subscribers.

void unset_mode_group_learn ()

Notifies all of the notification subscribers that group-learn is being turned off.

• bool is group learning ()

'Getter' function for member m_mode_group_learn

void set_and_copy_mute_group (int group)

When in group-learn mode, for active sequences, the mute-group settings are set based on the playing status of each sequence.

void start (bool state)

If JACK is not running, call inner start() with the given state.

• void stop ()

If JACK is not running, call inner_stop().

void start_jack ()

If JACK is supported, starts the JACK transport.

void stop_jack ()

If JACK is supported, stops the JACK transport.

void position_jack (bool state, midipulse tick=0)

If JACK is supported and running, sets the position of the transport.

• void off_sequences ()

For all active patterns/sequences, set the playing state to false.

void all_notes_off ()

For all active patterns/sequences, turn off its playing notes.

• void set_active (int seq, bool active)

Sets or unsets the active state of the given pattern/sequence number.

void set_was_active (int seq)

Sets was-active flags: main, edit, perf, and names.

void reset sequences (bool pause=false)

For all active patterns/sequences, get its playing state, turn off the playing notes, set playing to false, zero the markers, and, if not in playback mode, restore the playing state.

· void play (midipulse tick)

Plays all notes to the current tick.

void set_orig_ticks (midipulse tick)

For every pattern/sequence that is active, sets the "original tick" value for the pattern.

void set_beats_per_minute (int bpm)

Sets the value of the BPM into the master MIDI buss, after making sure it is squelched to be between 20 and 500.

void set_looping (bool looping)

'Setter' function for member m_looping

· int max active set () const

Checks the whole universe of sequences to determine the current last-active set, that is, the highest set that has any active sequences in it.

void launch_input_thread ()

Creates the input thread using input thread func().

void launch_output_thread ()

Creates the output thread using output_thread_func().

bool init_jack ()

Initializes JACK support, if SEQ64_JACK_SUPPORT is defined.

• bool deinit jack ()

Tears down the JACK infrastructure.

bool seq_in_playing_screen (int seq)

A helper function for determining if the mode group is in force, the playing screenset is the same as the current screenset, and the sequence is in the range of the playing screenset.

void is modified (bool flag)

'Setter' function for member m_is_modified

· bool valid_midi_control_seq (int seq) const

Checks the parameter against c_midi_controls.

bool is_screenset_valid (int screenset) const

Checks the screenset against m_max_sets.

void set_running (bool running)

'Setter' function for member m_running

void is_pattern_playing (bool flag)

'Setter' function for member m_is_pattern_playing

void set_playback_mode (bool playbackmode)

'Setter' function for member m playback mode

• int mute_group_offset (int track)

A helper function to calculate the index into the mute-group array, based on the desired track.

bool is_seq_valid (int seq) const

Provides common code to check for the bounds of a sequence number.

bool is_mseq_valid (int seq) const

Validates the sequence number, which is important since they're currently used as array indices.

bool install_sequence (sequence *seq, int seqnum)

A private helper function for add_sequence() and new_sequence().

void inner_start (bool state)

Locks on m_condition_var.

void inner_stop (bool midiclock=false)

Unconditionally, and without locking, clears the running status, resets the sequences, and sets m_usemidiclock false.

int clamp_track (int track) const

Provides common code to keep the track value valid.

• void set_all_key_events ()

Pass-along function for keys().set_all_key_events.

void set_all_key_groups ()

Pass-along function for keys().set_all_key_events.

void set_key_event (unsigned int keycode, long sequence_slot)

At construction time, this function sets up one keycode and one event slot.

void set_key_group (unsigned int keycode, long group_slot)

At construction time, this function sets up one keycode and one group slot.

Private Attributes

bool m_song_start_mode

If true, playback is done in Song mode, not Live mode.

· bool m start from perfedit

Indicates that, no matter what the current Song/Live setting, the playback was started from the perfedit window.

bool m_reposition

It seems that this member, if true, forces a repositioning to the left (L) tick marker.

· float m excell FF RW

TRD

• ff_rw_button_t m_FF_RW_button_type

TRE

· gui assistant & m gui support

Support for a wide range of GUI-related operations.

bool m mute group [c max sequence]

Mute group support.

· bool m armed saved

Indicates if the m_saved_armed_statuses[] values are the saved state of the sequences, and can be restored.

• bool m armed statuses [c max sequence]

Holds the "global" saved status of the playing tracks, for restoration after saving.

bool m_tracks_mute_state [c_seqs_in_set]

Holds the current mute states of each track.

• bool m_mode_group

If true, indicates that a mode group is selected, and playing statuses will be "memorized".

bool m_mode_group_learn

If true, indicates that a group learn is selected, which also "memorizes" a mode group, and notifies subscribers of a group-learn change.

int m_mute_group_selected

Selects a group to mute.

• int m_playing_screen

Playing screen support.

int m_playscreen_offset

Playing screen sequence number offset.

• sequence * m_seqs [c_max_sequence]

Provides a "vector" of patterns/sequences.

bool m_seqs_active [c_max_sequence]

Each boolean value in this array is set to true if a sequence is active, meaning that it will be used to hold some kind of MIDI data, even if only Meta events.

• bool m_was_active_main [c_max_sequence]

Each boolean value in this array is set to true if a sequence was active, meaning that it was found to be active at the time we were setting it to inactive.

• bool m_was_active_edit [c_max_sequence]

Each boolean value in this array is set to true if a sequence was active, meaning that it was found to be active at the time we were setting it to inactive.

bool m_was_active_perf [c_max_sequence]

Each boolean value in this array is set to true if a sequence was active, meaning that it was found to be active at the time we were setting it to inactive.

bool m_was_active_names [c_max_sequence]

Each boolean value in this array is set to true if a sequence was active, meaning that it was found to be active at the time we were setting it to inactive.

• bool m_sequence_state [c_max_sequence]

Saves the current playing state of each pattern.

mastermidibus m_master_bus

Provides our MIDI buss.

· int m_transpose

Holds the global MIDI transposition value.

pthread_t m_out_thread

Provides information for managing pthreads.

• pthread_t m_in_thread

Provides a "handle" to the input thread.

· bool m out thread launched

Indicates that the output thread has been started.

· bool m in thread launched

Indicates that the input thread has been started.

bool m_running

Indicates that playback is running.

bool m_is_pattern_playing

Indicates that a pattern is playing.

bool m_inputing

Indicates that events are being written to the MIDI input busses in the input thread.

bool m_outputing

Indicates that events are being written to the MIDI output busses in the output thread.

· bool m_looping

Indicates that status of the "loop" button in the performance editor.

· bool m_playback_mode

Specifies the playback mode.

• int m_ppqn

Holds the current PPQN for usage in various actions.

int m_beats_per_bar

Holds the beats/bar value as obtained from the MIDI file.

• int m_beat_width

Holds the beat width value as obtained from the MIDI file.

• int m_clocks_per_metronome

Augments the beats/bar and beat-width with the additional values included in a Time Signature meta event.

• int m_32nds_per_quarter

Augments the beats/bar and beat-width with the additional values included in a Time Signature meta event.

long m_us_per_quarter_note

Augments the beats/bar and beat-width with the additional values included in a Tempo meta event.

• midipulse m_one_measure

Holds the "one measure's worth" of pulses (ticks), which is normally m_ppqn*4 .

· midipulse m left tick

Holds the position of the left (L) marker, and it is first defined as 0.

midipulse m_right_tick

Holds the position of the right (R) marker, and it is first defined as the end of the fourth measure.

• midipulse m_starting_tick

Holds the starting tick for playing.

• midipulse m_tick

MIDI Clock support.

midipulse m_jack_tick

Let's try to save the last JACK pad structure tick for re-use with resume after pausing.

· bool m usemidiclock

More MIDI clock support.

• bool m_midiclockrunning

More MIDI clock support.

int m_midiclocktick

More MIDI clock support.

· int m_midiclockpos

More MIDI clock support.

• bool m_dont_reset_ticks

Support for pause, which does not reset the "last tick" when playback stops/starts.

std::string m_screen_set_notepad [c_max_sets]

Used in the mainwnd class to set the notepad text for the given set.

midi_control m_midi_cc_toggle [c_midi_controls]

Provides the settings of MIDI Toggle, as read from the "rc" file.

midi_control m_midi_cc_on [c_midi_controls]

Provides the settings of MIDI On, as read from the "rc" file.

midi_control m_midi_cc_off [c_midi_controls]

Provides the settings of MIDI Off, as read from the "rc" file.

· int m offset

Holds the current offset into the screen-sets.

· int m control status

Holds the OR'ed control status values.

· int m screenset

Indicates the number of the currently-selected screen-set.

int m_seqs_in_set

We will eventually replace c_seqs_in_set with this member, which defaults to the value of c_seqs_in_set.

• int m_max_sets

A replacement for the c_max_sets constant.

• int m_sequence_count

Keeps track of created sequences, whether or not they are active.

int m_sequence_max

A replacement for the c_max_sequence constant.

• int m_edit_sequence

Hold the number of the currently-in-edit sequence.

bool m_is_modified

It may be a good idea to eventually centralize all of the dirtiness of a performance here.

· condition var m condition var

A condition variable to protect playback.

jack_assistant m_jack_asst

A wrapper object for the JACK support of this application.

- bool m_have_undo
- std::vector< int > m_undo_vect

Holds ??? for undo operations.

- bool m have redo
- std::vector< int > m_redo_vect

Holds ??? for undo operations.

std::vector< performcallback * > m_notify

Static Private Attributes

· static midi_control sm_mc_dummy

Provides a dummy, inactive midi_control object to handle out-of-range midi_control indicies.

Friends

- · class jack_assistant
- class keybindentry
- · class mainwnd
- · class midifile
- · class optionsfile
- class options
- · class perfedit
- class perfroll
- void * input_thread_func (void *myperf)

Set up the performance, and set the process to realtime privileges.

void * output_thread_func (void *myperf)

Global functions defined in perform.cpp.

• int jack_sync_callback (jack_transport_state_t state, jack_position_t *pos, void *arg)

Global functions for JACK support and JACK sessions.

- int jack_process_callback (jack_nframes_t nframes, void *arg)
- void jack_shutdown (void *arg)
- void jack_timebase_callback (jack_transport_state_t state, jack_nframes_t nframes, jack_position_t *pos, int new_pos, void *arg)

The JACK timebase function defined here sets the JACK position structure.

• long get_current_jack_position (void *arg)

12.51.1 Detailed Description

It has way too many data members, one of them public. Might be ripe for refactoring. That has its own dangers, of course.

12.51.2 Member Enumeration Documentation

12.51.2.1 mute_op_t

enum seq64::perform::mute_op_t

Enumerator

MUTE_TOGGLE	
MUTE_OFF	
MUTE_ON	

12.51.2.2 ff_rw_button_t

enum seq64::perform::ff_rw_button_t

Enumerator

FF_RW_REWIND	
FF_RW_NONE	
FF_RW_FORWARD	

12.51.3 Constructor & Destructor Documentation

12.51.3.1 perform()

Also note that we have a little issue with the fact that various sequences (patterns) can potentially have different beats/measure and beat-width values.

Currently, when reading the MIDI file, the beats/minute value is obtained from the MIDI file, if present, and this value is passed to perform::set_beats_per_minute(), which forwards it to the master MIDI buss and JACK assistant objects. This Tempo setting comes from both the Tempo meta event in track 0, and from the Seq24's c_bpm SeqSpec section! This setting is now also made for the two Time Signature values.

Parameters

mygui	Provides access to the GUI assistant that holds many things, including the containers of keys and the "events" they provide. This is a base-class reference; for a real class, see the gui_assistant_gtk2 class in the seq_gtkmm2 GUI-specific library. Note that we access the m_gui_support member using the gui() accessor function.
ppqn	The default, choosable, or actual PPQN value.

12.51.3.2 ∼perform()

```
seq64::perform::~perform ()
```

Finally, any active or inactive (but allocated) patterns/sequences are deleted, and their pointers nullified.

12.51.4 Member Function Documentation

```
12.51.4.1 is_modified() [1/2]
bool seq64::perform::is_modified ( ) const [inline]

12.51.4.2 modify()

void seq64::perform::modify ( ) [inline]
```

The setter that will, is_modified(), is private. No one but perform and its friends should falsify this flag.

12.51.4.3 sequence_count()

```
int seq64::perform::sequence_count ( ) const [inline]
```

In many cases at startup, or when loading a file, there are no sequences yet, and still the code calls functions that try to access them.

12.51.4.4 sequence_max()

```
int seq64::perform::sequence_max ( ) const [inline]
```

12.51.4.5 is_control_status()

```
bool seq64::perform::is_control_status ( ) const [inline]
```

Returns

Returns true if the m_control_status value is non-zero, which means that there is a queue, replace, or snapshot functionality in progress.

12.51.4.6 set_edit_sequence()

Parameters

seqnum

Pass in -1 to disable the edit-sequence number unconditionally. Use unset_edit_sequence() to disable it if it matches the current edit-sequence number.

12.51.4.7 unset_edit_sequence()

```
void seq64::perform::unset_edit_sequence (
    int seqnum ) [inline]
```

Disables the edit-sequence number if it matches the parameter.

Parameters

seqnum The sequence number of the sequence to unset.

12.51.4.8 is_edit_sequence()

Parameters

seqnum

Tests the parameter against m_edit_sequence. Returns true if that member is not -1, and the parameter matches it.

```
12.51.4.9 get_beats_per_bar()
```

```
int seq64::perform::get_beats_per_bar ( ) const [inline]
```

12.51.4.10 set_beats_per_bar()

Parameters

bpm

Provides the value for beats/measure. Also used to set the beats/measure in the JACK assistant object.

12.51.4.11 get_beat_width()

```
int seq64::perform::get_beat_width ( ) const [inline]
```

12.51.4.12 set_beat_width()

Parameters

bw Provides the value for beat-width. Also used to set the beat-width in the JACK assistant object.

12.51.4.13 clocks_per_metronome() [1/2]

12.51.4.14 clocks_per_metronome() [2/2]

```
int seq64::perform::clocks_per_metronome ( ) const [inline]
```

12.51.4.15 set_32nds_per_quarter()

```
void seq64::perform::set_32nds_per_quarter ( int \ tpq \ ) \quad [inline]
```

12.51.4.16 get_32nds_per_quarter()

```
int seq64::perform::get_32nds_per_quarter ( ) const [inline]
```

```
12.51.4.17 us_per_quarter_note() [1/2]
void seq64::perform::us_per_quarter_note (
             long upqn ) [inline]
12.51.4.18 us_per_quarter_note() [2/2]
long seq64::perform::us_per_quarter_note ( ) const [inline]
12.51.4.19 gui() [1/2]
const gui_assistant& seq64::perform::gui ( ) const [inline]
12.51.4.20 gui() [2/2]
gui_assistant& seq64::perform::gui ( ) [inline]
12.51.4.21 keys() [1/2]
const keys_perform& seq64::perform::keys ( ) const [inline]
12.51.4.22 keys() [2/2]
keys_perform& seq64::perform::keys ( ) [inline]
12.51.4.23 master_bus()
mastermidibus& seq64::perform::master_bus ( ) [inline]
12.51.4.24 filter_by_channel()
void seq64::perform::filter_by_channel (
             bool flag ) [inline]
12.51.4.25 is_running()
bool seq64::perform::is_running ( ) const [inline]
12.51.4.26 is_pattern_playing() [1/2]
bool seq64::perform::is_pattern_playing ( ) const [inline]
```

```
12.51.4.27 toggle_song_start_mode()
bool seq64::perform::toggle_song_start_mode ( ) [inline]
12.51.4.28 song_start_mode() [1/2]
void seq64::perform::song_start_mode (
             bool flag ) [inline]
12.51.4.29 song_start_mode() [2/2]
bool seq64::perform::song_start_mode ( ) const [inline]
12.51.4.30 is_jack_running()
bool seq64::perform::is_jack_running ( ) const [inline]
12.51.4.31 is_jack_master()
bool seq64::perform::is_jack_master ( ) const [inline]
12.51.4.32 enregister()
void seq64::perform::enregister (
             performcallback * pfcb ) [inline]
Parameters
 pfcb
       Provides the pointer to the performance callback.
12.51.4.33 toggle_jack_mode()
void seq64::perform::toggle_jack_mode ( ) [inline]
12.51.4.34 set_jack_mode()
bool seq64::perform::set_jack_mode (
             bool jack_button_active )
```

Note that we moved some of the code from perfedit::set_jack_mode() [the seq32 version] to this function.

Jack button active indicates if the peneur JACK button shows it is active.	jack button active	Indicates if the perfedit JACK button shows it is active.
--	--------------------	---

Returns

Returns true if JACK is running currently, and false otherwise.

http://www.blitter.com/~russtopia/MIDI/~jglatt/tech/midispec/wheel.htm

Two data bytes follow the status. The two bytes should be combined together to form a 14-bit value. The first data byte's bits 0 to 6 are bits 0 to 6 of the 14-bit value. The second data byte's bits 0 to 6 are really bits 7 to 13 of the 14-bit value. In other words, assuming that a C program has the first byte in the variable First and the second data byte in the variable Second, here's how to combine them into a 14-bit value (actually 16-bit since most computer CPUs deal with 16-bit, not 14-bit, integers).

Parameters

b0	The first byte to be combined.
b1	The second byte to be combined.

Returns

Returns the bytes basically OR'd together.

12.51.4.38 FF_rewind()

```
void seq64::perform::FF_rewind ( )
```

```
12.51.4.39 FF_RW_timeout()
bool seq64::perform::FF_RW_timeout ( )
This function is used in the free function version of FF_RW_timeout() as a callback to the gtk_timeout() function.
12.51.4.40 start_from_perfedit() [1/2]
void seq64::perform::start_from_perfedit (
              bool flag ) [inline]
12.51.4.41 start_from_perfedit() [2/2]
bool seq64::perform::start_from_perfedit ( ) const [inline]
12.51.4.42 set_follow_transport()
void seq64::perform::set_follow_transport (
             bool flag ) [inline]
12.51.4.43 get_follow_transport()
bool seq64::perform::get_follow_transport ( ) const [inline]
12.51.4.44 toggle_follow_transport()
void seq64::perform::toggle_follow_transport ( ) [inline]
12.51.4.45 set_reposition()
void seq64::perform::set_reposition (
             bool postype = true ) [inline]
12.51.4.46 ff_rw_type() [1/2]
ff_rw_button_t seq64::perform::ff_rw_type ( ) [inline]
12.51.4.47 ff_rw_type() [2/2]
void seq64::perform::ff_rw_type (
             ff_rw_button_t button_type ) [inline]
12.51.4.48 rewind()
void seq64::perform::rewind (
              bool press ) [inline]
```

press If true, the status is set to FF_RW_REWIND, otherwise it is set to FF_RW_NONE.

12.51.4.49 fast_forward()

Parameters

press If true, the status is set to FF_RW_FORWARD, otherwise it is set to FF_RW_NONE.

12.51.4.50 reposition()

Used only in perfroll :: on_key_press_event() to implement the Seq32 pointer-position feature.

Parameters

tick Provides the position value to be set.

12.51.4.51 clear_all()

```
bool seq64::perform::clear_all ( )
```

The mainwand module calls this function. Note that perform now handles the "is modified" flag on behalf of all external objects, to centralize and simplify the dirtying of a MIDI tune.

Anything else to clear? What about all the other sequence flags? We can beef up delete_sequence() for them, at some point.

Added stazed code from 1.0.5 to abort clearing if any of the sequences are in editing.

Returns

Returns true if the clear-all operation could be performed. If false, then at least one active sequence was in editing mode.

12.51.4.52 launch()

This function is called in main(). We collected all the calls here as a simplification, and renamed it because it is more than just initialization. This function must be called after the perform constructor and after the configuration file and command-line configuration overrides.

ppqn

Provides the PPQN value, which is either the default value (192) or is read from the "user" configuration file.

12.51.4.53 new_sequence()

Then it activates the pattern [this is done in the install_sequence() function]. It doesn't deal with thrown exceptions.

This function is called by the seqmenu and mainwid objects to create a new sequence. We now pass this sequence to install_sequence() to better handle potential memory leakage, and to make sure the sequence gets counted. Also, adding a new sequence from the user-interface is a significant modification, so the "is modified" flag gets set.

Change Note ca 2016-05-15 If enabled, wire in the MIDI buss override.

Parameters

seq The prospective sequence number of the new sequence.

12.51.4.54 add_sequence()

No check is made for a null pointer, but the install sequence() call will make sure such a pointer is officially logged.

This function checks for the preferred sequence number. This is the number that was specified by the Sequence Number meta-event for the current track. If the preferred sequence number is in the valid range (0 to m_sequence — max) and it is not active, add it and activate it. Otherwise, iterate through all patterns from prefnum to m_ sequence _ max and add and activate the first one that is not active, and then finish.

Finally, note that this function is used only by midifile, when reading in a MIDI song. Therefore, the "is modified" flag is *not* set by this function; loading a sequence from a file is not a modification that should lead to a prompt for saving the file later.

Todo Shouldn't we wrap around the sequence list if we can't find an empty sequence slot after prefnum?

Todo This function needs some deeper analysis against the original, in my opinion.

Warning

The logic of the if-statement in this function was such that *prefnum* could be out-of-bounds in the else-clause. We reworked the logic to be airtight. This bug was caught by gcc 4.8.3 on CentOS, but not on gcc 4.9.3 on Debian Sid!

seq	The pointer to the pattern/sequence to add.	1
prefnum	The preferred sequence number of the pattern, as explained above. If this value is out-of-range, then it is basically ignored.	

12.51.4.55 delete_sequence()

We now also solidify the deletion by setting the pointer to null after deletion, so it will blow up if accidentally accessed. The final act is to raise the "is modified" flag, since deleting an existing sequence is always a significant modification.

Now, this function obviously sets the "active" flag for the sequence to false. But there are a few other flags that are not modified; shouldn't we also falsify them here?

Parameters

seq The sequence number of the sequence to be deleted. It is valid	dated.
--	--------

12.51.4.56 is_sequence_in_edit()

Parameters

seq Provides the sequence number to be checked.

Returns

Returns truen if the sequence's get_editing() call returns true. Otherwise, false is returned, which can also indicate an illegal sequence number.

12.51.4.57 clear_sequence_triggers()

Parameters

seq | Provides the desired sequence. The is_active() function validates this value.

```
12.51.4.58 print_triggers()
void seq64::perform::print_triggers ( ) const

12.51.4.59 finish()
void seq64::perform::finish ( ) [inline]
```

A minor simplification for the main() routine, hides the JACK support macro.

Parameters

tick Provides the current JACK tick (pulse) value to set.

```
12.51.4.63 set_left_tick()
```

We let the caller determine if this setting is a modification. If the left tick is later than the right tick, the right tick is move to one measure past the left tick.

Todo The perform::m_one_measure member is currently hardwired to PPQN * 4.

Parameters

tick	The tick (MIDI pulse) at which to place the left tick. If the left tick is greater than or equal to the right tick, then the right ticked is moved forward by one "measure's length" ($m_ppqn * 4$) past the left tick.
setstart	If true (the default, and long-standing implicit setting), then the starting tick is also set to the left tick.

tick Provides the starting JACK tick (pulse) value to set.

```
12.51.4.66 get_start_tick()
```

```
midipulse seq64::perform::get_start_tick ( ) const [inline]
```

12.51.4.67 set_right_tick()

This setting is made only if the tick parameter is at or beyond the first measure. We let the caller determine is this setting is a modification.

Parameters

tick	The tick (MIDI pulse) at which to place the right tick. If less than or equal to the left tick setting, then the left tick is backed up by one "measure's worth" (m_ppqn * 4) worth of ticks from the new right tick.
setstart	If true (the default, and long-standing implicit setting), then the starting tick is also set to the left tick, if that got changed.

12.51.4.68 get_right_tick()

```
midipulse seq64::perform::get_right_tick ( ) const [inline]

12.51.4.69 left_right_size()

double seq64::perform::left_right_size ( ) const [inline]
```

Returns

Returns the difference between the right and left tick, cast to double.

12.51.4.70 is_active()

Parameters

seq

The pattern number. It is checked for invalidity. This can lead to "too many" (i.e. redundant) checks, but we're trying to centralize such checks in this function.

Returns

Returns the value of the active-flag, or false if the sequence was invalid or null.

```
12.51.4.71 apply_song_transpose()
```

```
void seq64::perform::apply_song_transpose ( )
```

12.51.4.72 set_transpose()

```
void seq64::perform::set_transpose ( int \ t \ ) \ [inline]
```

12.51.4.73 get_transpose()

```
int seq64::perform::get_transpose ( ) const [inline]
```

12.51.4.74 get_beats_per_minute()

```
int seq64::perform::get_beats_per_minute ( ) [inline]
```

Returns

Returns the value of beats/minute from the master buss.

12.51.4.75 set_sequence_control_status()

Then the given status is OR'd into the m_control_status.

Parameters

status	The status to be used.
Siaius	i i i c status to be useu.

12.51.4.76 unset_sequence_control_status()

```
void seq64::perform::unset_sequence_control_status ( int \ status \ )
```

Then the given status is reversed in m_control_status.

Parameters

status	The status to be used.
--------	------------------------

12.51.4.77 sequence_playing_toggle()

If the m_control_status is c_status_queue, then the sequence's toggle_queued() function is called. Otherwise, if it is c_status_replace, then the status is unset, and all sequences (?) are turned off. Then the sequence's toggle-playing() function is called.

Parameters

seq The sequence number of the sequence to be potentially toggled.

12.51.4.78 sequence_playing_change()

Used for the implementation of sequence_playing_on() and sequence_playing_off().

Parameters

seq	The number of the sequence to be turned off.
on	True if the sequence is to be turned on, false if it is to be turned off.

12.51.4.79 sequence_playing_on()

```
void seq64::perform::sequence_playing_on (
    int seq ) [inline]
```

Parameters

seq The sequence number of the sequence to turn on.

12.51.4.80 sequence_playing_off()

Parameters

seq The sequence number of the sequence to turn off.

12.51.4.81 mute_all_tracks()

Covers tracks from 0 to m_sequence_max.

We have to also set the sequence's playing status, in opposition to the mute status, in order to see the sequence status change on the user-interface. HMMMMMM.

Parameters

flag If true (the default), the song-mute of the sequence is turned on. Otherwise, it is turned off.

```
12.51.4.82 toggle_all_tracks()
```

```
void seq64::perform::toggle_all_tracks ( )
```

Covers tracks from 0 to m_sequence_max.

12.51.4.83 armed_saved()

```
bool seq64::perform::armed_saved ( ) const [inline]
```

12.51.4.84 toggle_playing_tracks()

```
void seq64::perform::toggle_playing_tracks ( )
```

12.51.4.85 mute_screenset()

Parameters

flag If true (the default), the song-mute of the sequence is turned on. Otherwise, it is turned off.	ss	The screen-set to be operated upon.	
Generated by Doxyg	flag		erated by Doxygen

12.51.4.86 output_func()

```
void seg64::perform::output_func ( )
```

This function is called by the free function output_thread_func(). Here's how it works:

```
It runs while m_outputing is true.MORE TO COME. Yeah, a lot more to come. It is a complex function.
```

Change Note ca 2016-01-26 Hurray, seq24 is coming back to life! We see that there is a fix for clock tick drift here, which relies on using long and long long values. See the Changelog for seq24 0.9.3.

- 1. Get delta time (current last).
- 2. Get delta ticks from time.
- Add to current_ticks.
- 4. Compute prebuffer ticks.
- 5. Play from current tick to prebuffer.

Figure out how much time we need to sleep, and do it.

Now we want to trigger every c_thread_trigger_width_us, and it took us delta_us to play(). Also known as the "sleeping_us".

Check MIDI clock adjustment. Note that we replaced "60000000.0f / m_ppqn / bpm" with a call to a function. We also removed the "f" specification from the constants.

```
12.51.4.87 input_func()
```

```
void seq64::perform::input_func ( )
```

Stazed:

```
http://www.blitter.com/~russtopia/MIDI/~jglatt/tech/midispec/ssp.htm

Example: If a Song Position value of 8 is received, then a sequencer
(or drum box) should cue playback to the third quarter note of the
song. (8 MIDI beats * 6 MIDI clocks per MIDI beat = 48 MIDI Clocks.
Since there are 24 MIDI Clocks in a quarter note, the first quarter
occurs on a time of 0 MIDI Clocks, the second quarter note occurs upon
the 24th MIDI Clock, and the third quarter note occurs on the 48th
MIDI Clock).

8 MIDI beats * 6 MIDI clocks per MIDI beat = 48 MIDI Clocks.
```

12.51.4.88 set_group_mute_state()

The index value is the track number offset by the number of the selected mute group (which is equivalent to a set number) times the number of sequences in a set. This function is used in midifile and optionsfile when parsing the file to get the initial mute-groups.

gtrack	The number of the track to be muted/unmuted.
muted	This boolean indicates the state to which the track should be set.

12.51.4.89 get_group_mute_state()

Uses the multi-group_offset() function. This function is used in midifile and optionsfile when writing the file to get the initial multi-groups.

Parameters

gtrack	The number of the track for which the state is to be obtained. Like set_group_mute_state(), this value	1
	is offset by adding m_mute_group_selected * m_seqs_in_set.	

Returns

Returns the desired m_mute_group[] value.

12.51.4.90 set_offset()

```
void seq64::perform::set_offset (
        int offset ) [inline]
```

Sets m_offset = offset * c_mainwnd_rows * c_mainwnd_cols.

Parameters

12.51.4.91 get_offset()

```
int seq64::perform::get_offset ( ) const [inline]
```

12.51.4.92 save_playing_state()

```
void seq64::perform::save_playing_state ( )
```

Inactive patterns get the value set to false. Used in unsetting the snapshot status (c_status_snapshot).

```
12.51.4.93 restore_playing_state()
void seq64::perform::restore_playing_state ( )
Used in unsetting the snapshot status (c_status_snapshot).
12.51.4.94 key_name()
std::string seq64::perform::key_name (
              unsigned int k ) const [inline]
Parameters
    The key number for which to return the string name of the key.
12.51.4.95 get_key_events()
keys_perform::SlotMap& seq64::perform::get_key_events ( ) [inline]
12.51.4.96 get_key_groups()
keys_perform::SlotMap& seq64::perform::get_key_groups ( ) [inline]
12.51.4.97 get_key_events_rev()
keys_perform::RevSlotMap& seq64::perform::get_key_events_rev ( ) [inline]
12.51.4.98 get_key_groups_rev()
keys_perform::RevSlotMap& seq64::perform::get_key_groups_rev () [inline]
12.51.4.99 show_ui_sequence_key() [1/2]
bool seq64::perform::show_ui_sequence_key ( ) const [inline]
Used in mainwid, options, optionsfile, userfile, and perform.
12.51.4.100 show_ui_sequence_key() [2/2]
void seq64::perform::show_ui_sequence_key (
             bool flag ) [inline]
```

flag | Provides the flag to set into keys().show_ui_sequence_key().

```
bool seq64::perform::show_ui_sequence_number ( ) const [inline]
```

Used in mainwid, optionsfile, and perform.

12.51.4.101 show_ui_sequence_number() [1/2]

Parameters

flag | Provides the value to set into keys().show_ui_sequence_number().

12.51.4.103 lookup_keyevent_key()

If we're not in legacy mode, then we adjust for the screenset, so that screensets greater than 0 can also show the correct key name, instead of a question mark.

Legacy seq24 already responds to the toggling of the mute state via the shortcut keys even if screenset > 0, but it shows the question mark.

Parameters

seqnum	The number of the sequence for which to return the event key.
--------	---

Returns

Returns the desired key. If there is no such value, then the period ('?') character is returned.

12.51.4.104 lookup_keyevent_seq()

The inverse of lookup_keyevent_key().

kevcode	The number of the event key for which to return the configured sequence number.
noyocac	The number of the event key for which to return the comigarou coquence number.

Returns

Returns the desired sequence. If there is no such value, then a sequence number of 0 is returned.

12.51.4.105 lookup_keygroup_key()

Parameters

Returns

Returns the desired key. If there is no such value, then the period ('.') character is returned.

12.51.4.106 lookup_keygroup_group()

The inverse of lookup_keygroup_key().

Parameters

keycode The number of the group key for which to return the configured sequence num

Returns

Returns the desired group number. If there is no such value, then a group number of 0 is returned.

12.51.4.107 start_playing()

```
void seq64::perform::start_playing (
                bool songmode = false )
```

We've reversed the start() and start_jack() calls so that JACK is started first, to match all of the other use-cases for playing that we've found in the code. Note that the complementary function, stop_playing(), is an inline function defined in the header file.

The perform::start() function passes its boolean flag to perform::inner_start(), which sets the playback mode to that flag; if that flag is false, that turns off "song" mode. So that explains why mute/unmute is disabled.

Playback use cases:

These use cases are meant to apply to either a Seq32 or a regular build of Sequencer64, eventually. Currently, the regular build does not have a concept of a "global" perform song-mode flag.

- -# mainwnd.
 - -# Play. If the perform song-mode is "Song", then use that mode.
 Otherwise, use "Live" mode.
 - -# Stop. This action is modeless here. In ALSA, it will cause a rewind (but currently sequently doesn't rewind until Play is clicked, a minor bug).
 - -# Pause. Same processing as Play or Stop, depending on current status. When stopping, the progress bars in seqroll and perfroll remain at their current point.
- -# perfedit.
 - -# Play. Override the current perform song-mode to use "Song".
 - -# Stop. Revert the perfedit setting, in case play is restarted or resumed via mainwnd.
 - -# Pause. Same processing as Play or Stop, depending on current status.
- -# ALSA versus JACK. One issue here is that, if JACK isn't "running" at all (i.e. we are in ALSA mode), then we cannot be JACK Master.

Parameters

songmode

Indicates if the caller wants to start the playback in Song mode (sometimes erroneously referred to as "JACK mode"). In the seq32 code at GitHub, this flag was identical to the "global_jack_start_mode" flag, which is true for Song mode, and false for Live mode. False disables Song mode, and is the default, which matches seq24. Generally, we pass true in this parameter if we're starting playback from the perfedit window. It alters the m_start_from_perfedit member, not the m_song_start_mode member (which replaces the global flag now).

12.51.4.108 pause_playing()

Currently almost the same as stop_playing(), but expanded as noted in the comments so that we ultimately have more granular control over what happens. We're researching the whole sequence of stopping and starting, and it can be tricky to make correct changes.

We still need to make restarting pick up at the same place in ALSA mode; in JACK mode, JACK transport takes care of that feature.

Parameters

songmode

Indicates that, if resuming play, it should play in Song mode (true) or Live mode (false). See the comments for the start playing() function.

12.51.4.109 stop_playing()

```
void seq64::perform::stop_playing ( )
```

Stops playback, turns off the (new) m_dont_reset_ticks flag, and set the "is-pattern-playing" flag to false. With stop, reset the start-tick to either the left-tick or the 0th tick (to be determined, currently resets to 0).

12.51.4.110 start_key()

```
void seq64::perform::start_key (
          bool songmode = false )
```

Meant to be used by GUIs to unify the treatment of keys versus buttons.

Parameters

songmode The live/play mode parameter to be passed along to the key processor. Defaults to false (live mode).

12.51.4.111 pause_key()

```
void seq64::perform::pause_key (
          bool songmode = false )
```

Meant to be used by GUIs to unify the treatment of keys versus buttons.

Parameters

songmode	The live/play mode parameter to be passed along to the key processor, when starting playback.
	Defaults to false (live mode).

12.51.4.112 stop_key()

```
void seq64::perform::stop_key ( )
```

Meant to be used by GUIs to unify the treatment of keys versus buttons.

12.51.4.113 learn_toggle()

```
void seq64::perform::learn_toggle ( ) [inline]
```

12.51.4.114 decrement_beats_per_minute()

```
int seq64::perform::decrement_beats_per_minute ( ) [inline]
```

Actually does a lot of work in those function calls.

12.51.4.115 increment_beats_per_minute()

```
int seq64::perform::increment_beats_per_minute ( ) [inline]
```

Actually does a lot of work in those function calls.

12.51.4.116 decrement_screenset()

```
int seq64::perform::decrement_screenset ( ) [inline]
```

12.51.4.117 increment_screenset()

```
int seq64::perform::increment_screenset ( ) [inline]
```

12.51.4.118 highlight()

This setting is currently a build-time option, but could be made a run-time option later.

Parameters

seq Provides a reference to the desired sequence.

12.51.4.119 is_smf_0()

Parameters

seq Provides a reference to the desired sequence.

12.51.4.120 get_sequence() [1/2]

This is the const version.

Parameters

seq The prospective sequence number.

Returns

Returns the value of m_seqs[seq] if seq is valid. Otherwise, a null pointer is returned.

seq The prospective sequence number.

Returns

Returns the value of m_seqs[seq] if seq is valid. Otherwise, a null pointer is returned.

12.51.4.122 sequence_key() void seq64::perform::sequence_key (int seq)

This function is use in mainwnd when toggling the mute/unmute setting using keyboard keys.

Parameters

seq The sequence's control-key number, which is relative to the current screen-set.

12.51.4.123 sequence_label()

This string goes on the bottom-left of those user-interface elements.

The format of this string is something like the following example, depending on the "show sequence numbers" option. The values shown are, in this order, sequence number (if allowed), buss number, channel number, beats per bar, and beat width.

```
No sequence number: 31-16 4/4
Sequence number: 9 31-16 4/4
```

The sequence number and buss number are re 0, while the channel number is displayed re 1, unless it is an SMF 0 null channel (0xFF), in which case it is 0.

Note

Later, we could add the sequence hot-key to this string, though showing that is not much use in perfnames. Also, this function is a stilted mix of direct access and access through sequence number.

seq

Provides the reference to the sequence, use for getting the sequence parameters to be written to the label string.

Returns

Returns the filled in label if the sequence is active. Otherwise, an empty string is returned.

12.51.4.124 set_input_bus()

This function is called by options::input_callback().

Tricky Code See the bus parameter. We should provide two separate functions for this feature, but it is already combined into one input-callback function with a lot of other functionality in the options module.

Parameters

bus	If this value is greater than SEQ64_DEFAULT_BUSS_MAX (32), then it is treated as a user-interface flag (PERFORM_KEY_LABELS_ON_SEQUENCE or PERFORM_NUM_LABELS_ON_SEQUENCE)
	that causes all the sequences to be dirtied, and thus get redrawn with the new user-interface setting.
active	Indicates whether the buss or the user-interface feature is active or inactive.

12.51.4.125 mainwnd_key_event()

This function handles the keys for the functions of replace, queue, keep-queue, snapshots, toggling mute groups, group learn, and playing screenset. For further keystroke processing, see mainwand :: on_key_press_event().

Keys not handled here are handled in mainwnd: bpm up & down; screenset up & down.

Parameters

k The keystroke object to be handled.

Returns

Returns true if the key was handled.

12.51.4.126 perfroll_key_event()

```
bool seq64::perform::perfroll_key_event (
```

```
const keystroke & k,
int drop_sequence )
```

It handles the Ctrl keys for cut, copy, paste, and undo.

The "is modified" flag is raised if something is deleted, but we cannot yet handle the case where we undo all the changes. So, for now, we play it safe with the user, even if the user gets annoyed because he knows that he undid all the changes.

Parameters

k	The keystroke object to be handled.
drop_sequence	Provides the index of the sequence whose selected trigger is to be cut, copied, or pasted.
	Undo and redo are now supported.

Returns

Returns true if the key was handled.

12.51.4.127 playback_key_event()

To be used in mainwnd, perfedit, and seqroll.

The start/end key may be the same key (e.g. Space) to allow toggling when the same key is mapped to both triggers.

Checking is_running() may not work completely in JACK.

Change Note layk 2016-10-11 Issue #42 to prevent inadvertent step-edit in sequence :: stream_event(). We did it slightly different to save a little code; also found a spot that was missed.

Parameters

k	Provides the encapsulated keystroke to check.
songmode	Provides the "jack flag" needed by the mainwnd, seqroll, and perfedit windows. Defaults to false,
	which disables Song mode, and enables Live mode. But using Song mode seems to make the
	pause key not work in the performance editor.

Returns

Returns true if the keystroke matched the start, stop, or (new) pause keystrokes. Generally, no further keystroke processing is needed in this case.

12.51.4.128 move_triggers()

direction | Specifies the desired direction; false = left, true = right.

```
12.51.4.129 copy_triggers()
void seq64::perform::copy_triggers ( )
```

This copies the triggers between the L marker and R marker to the R marker.

int track = SEQ64_ALL_TRACKS)

```
12.51.4.130 push_trigger_undo()
void seq64::perform::push_trigger_undo (
```

Too bad we cannot yet keep track of all the undoes for the sake of properly handling the "is modified" flag.

This function now has a new parameter. Not added to this function is the seemingly redundant undo-push the seq32 code does; is this actually a seq42 thing?

Also, there is still an issue with our undo-handling for a single track. See pop_trigger_undo().

Parameters

track

A new parameter (found in the stazed seq32 code) that allows this function to operate on a single track. A parameter value of SEQ64_ALL_TRACKS (-1, the default) implements the original behavior.

```
12.51.4.131 pop_trigger_undo()
void seq64::perform::pop_trigger_undo ( )
```

Todo Look at seq32/src/perform.cpp and the perform :: push_trigger_undo(track) function, which has a track parameter that has a -1 values the supports all tracks. It requires two new vectors (one for undo, one for redo), two new flags (likewise). We've put this code in place, no longer macroed out, now permanent.

See the sequence::is_dirty_main() function.

seq The pattern number. It is checked for validity.

Returns

Returns the was-active-main flag value, before setting it to false. Returns false if the pattern was invalid.

12.51.4.134 is_dirty_edit()

Parameters

seq The pattern number. It is checked for validity.

Returns

Returns the was-active-edit flag value, before setting it to false. Returns false if the pattern was invalid.

12.51.4.135 is_dirty_perf()

Parameters

seq The pattern number. It is checked for validity.

Returns

Returns the was-active-perf flag value, before setting it to false. Returns false if the pattern/sequence number was invalid.

12.51.4.136 is_dirty_names()

Parameters

seq The pattern number. It is checked for validity.

Returns

Returns the was-active-names flag value, before setting it to false. Returns false if the pattern/sequence number was invalid.

12.51.4.137 is_exportable()

Parameters

seq The index of the desired sequence.

Returns

Returns true if the sequence has the three properties noted above.

12.51.4.138 set_screenset()

It's not clear that we need to set the "is modified" flag just because we changed the screen set, so we don't.

As a new feature, we would like to queue-mute the previous screenset, and queue-unmute the newly-selected screenset. Still working on getting it right.

Parameters

SS

The index of the desired new screen set. It is forced to range from 0 to m_max_sets - 1. The clamping seems weird, but hews to seq24. What it does is let the user wrap around the screen-sets in the user interface.

12.51.4.139 get_screenset()

```
int seq64::perform::get_screenset ( ) const [inline]
```

12.51.4.140 get_playing_screenset()

```
int seq64::perform::get_playing_screenset ( ) const [inline]
```

12.51.4.141 have_undo()

```
bool seq64::perform::have_undo ( ) const [inline], [private]
```

12.51.4.142 set_have_undo()

Once it is set, it remains set, unless cleared by saving the file.

12.51.4.143 have_redo()

```
bool seq64::perform::have_redo ( ) const [inline], [private]
```

12.51.4.144 set_have_redo()

```
void seq64::perform::set_have_redo (
    bool redo ) [inline], [private]
```

12.51.4.145 split_trigger()

Parameters

seqnum	Indicates the sequence that needs to have its trigger split.
tick	The MIDI pulse number at which the trigger should be split.

12.51.4.146 get_max_trigger()

```
midipulse seq64::perform::get_max_trigger ( ) [private]
```

Returns

Returns the highest trigger value, or zero. It is not clear why this function doesn't return a "no trigger found" value. Is there always at least one trigger, at 0?

12.51.4.147 collapse()

```
void seq64::perform::collapse ( ) [inline], [private]
```

12.51.4.148 copy()

```
void seq64::perform::copy ( ) [inline], [private]
```

12.51.4.149 expand()

```
void seq64::perform::expand ( ) [inline], [private]

12.51.4.150 midi_control_toggle()
```

Parameters

seq

Provides the index to pass to valid_midi_control_seq() to obtain a control value (such as c_midi_control_bpm_up) to use to retrieve the desired midi_control object. Note that this value is unsigned simply to make the legality check of the parameter easier.

Returns

Returns the "toggle" value if the sequence is valid, and a reference to sm_mc_dummy otherwise.

12.51.4.151 midi_control_on()

Parameters

seq

Provides the index to pass to valid_midi_control_seq() to obtain a control value (such as c_midi_control_bpm_up) to use to retrieve the desired midi_control object.

Returns

Returns the "on" value if the sequence is valid, and a reference to sm mc dummy otherwise.

12.51.4.152 midi_control_off()

Parameters

seq | Provides a control value (such as c_midi_control_bpm_up) to use to retrieve the desired midi_control object.

Returns

Returns the "off" value if the sequence is valid, and a reference to sm_mc_dummy otherwise.

12.51.4.153 handle_midi_control()

Parameters

ctrl	The MIDI control value to use to perform an operation.
state	The state of the control, used with the following
	values:

```
c_midi_control_mod_replace
c_midi_control_mod_snapshot
c_midi_control_mod_queue
c_midi_control_mod_gmute
c_midi_control_mod_glearn
```

12.51.4.154 get_screen_set_notepad()

Parameters

screenset	The ID number of the string set, an index into the m_screen_set_notepad[] array. This value is
	validated.

Returns

Returns a reference to the desired string, or to an empty string if the screen-set number is invalid.

12.51.4.155 current_screen_set_notepad()

screenset	The ID number of the string set, an index into the m_screen_set_xxx[] arrays.
notepad	Provides the string date to copy into the notepad. Not sure why a pointer is used, instead of nice
	"const std::string &" parameter. And this pointer isn't checked. Fixed.

```
12.51.4.157 set_screen_set_notepad() [2/2]
void seq64::perform::set_screen_set_notepad (
```

const std::string & note) [inline], [private]

Parameters

note The string value to set into the notepad text.

12.51.4.158 set_playing_screenset()

```
void seq64::perform::set_playing_screenset ( ) [private]
```

This function is called when one of the snapshot keys is pressed.

For each value up to m_seqs_in_set (32), the index of the current sequence in the current screen set (m_playing ← _screen) is obtained. If the sequence is active and the sequence actually exists, it is processed; null sequences are no longer flagged as an error, they are just ignored.

Modifies m_playing_screen, m_playscreen_offset, stores the current playing-status of each sequence in m_tracks ← _mute_state[], and then calls mute_group_tracks(), turns on unmuted tracks in the current screen-set.

Basically, this function retrieves and saves the playing status of the sequences in the current play-screen, sets the play-screen to the current screen-set, and then mutes the previous play-screen. It is called via the c_midi_control __play_ss value or via the set-playing-screen-set keystroke.

12.51.4.159 any_group_unmutes()

```
bool seq64::perform::any_group_unmutes ( ) const [private]
```

Returns

Returns true if there are any unmute statuses in the mute-group array. If they're all zero, we don't need to save them

12.51.4.160 mute_group_tracks()

```
void seq64::perform::mute_group_tracks ( ) [private]
```

It loops through every screen-set. In each screen-set, it acts on each active sequence. If the active sequence is in the current "in-view" screen-set (m_screenset as opposed to m_playing_screen), and its m_track_mute_state[] is true, then the sequence is turned on, otherwise it is turned off.

Change Note tdeagan 2015-12-22 via git pull. Replaced m_playing_screen with m_screenset.

It seems to us that the for (g) clause should have g range from 0 to m_max_sets, not m_seqs_in_set.

12.51.4.161 select_and_mute_group()

Called in perform and in mainwnd.

group Provides the group number for the group to be muted.

12.51.4.162 set_song_mute()

The sequence::set_song_mute() and toggle_song_mute() functions do all the work, including mp-dirtying the sequence.

We've modified this function to call mute_all_tracks() and toggle_all_tracks() in order to consolidate the code and (cough cough) fix a bug in this functionality from the mainwind menu.

Parameters

op | Provides the "flag" that indicates if this function is to set mute on, off, or to toggle the mute status.

12.51.4.163 set_mode_group_mute()

```
void seq64::perform::set_mode_group_mute ( ) [inline], [private]
```

12.51.4.164 unset_mode_group_mute()

```
void seq64::perform::unset_mode_group_mute ( ) [inline], [private]
```


Then, no matter what, it makes the desired mute-group the selected mute-group. Compare to set_and_copy_
mute_group().

One thing to note is that, once saved, then, if used, it is applied to the current screen-set, even if it is not the screen-set whose playing status were saved.

Parameters

mutegroup	The number of the desired mute group, clamped to be between 0 and m_seqs_in_set-1.
	Obviously, it is the set whose state is to be stored, if in group-learn mode.

12.51.4.166 set_mode_group_learn()

```
void seq64::perform::set_mode_group_learn ( ) [private]
```

This function is called via a MIDI control c_midi_control_mod_glearn and via the group-learn keystroke.

```
12.51.4.167 unset_mode_group_learn()
void seq64::perform::unset_mode_group_learn ( ) [private]
```

Then unsets the group-learn mode flag. This function is called via a MIDI control c_midi_control_mod_glearn, via the group-learn keystroke, and in mainwnd::on_key_press_event(), to end the group-learn mode.

Shouldn't this function also call this one, to perfectly complement set_mode_group_learn: unset_mode_group_ complement set_mode_group_learn: unset_mode_group_ complement set_mode_group_ complement set_mode_grou

Then the mute-group is stored in m_tracks_mute_state[], which holds states for only the number of sequences in a set.

Compare to select_group_mute(); its main difference is that it will at least copy the states even if not in group-learn mode. And, if in group-learn mode, it will grab the playing states of the sequences before copying them.

This function is used only once, in select_and_mute_group(). It used to be called just select_mute_group(), but that's too easy to confuse with select_group_mute().

Change Note tdeagan 2015-12-22 via git pull: git pull https://github.com/TDeagan/sequencer64.

git mute_groups m_screenset replaces m_playscreen_offset.

Parameters

mutegroup	Provides the mute-group to select.

12.51.4.170 start()

Parameters

songmode If true, playback is to be in Song mode. Otherwise, it is to be in Live mode.

```
12.51.4.171 stop()
```

```
void seq64::perform::stop ( ) [private]
```

The logic seems backward here, in that we call inner_stop() if JACK is not running. Or perhaps we misunderstand the meaning of m_jack_running?

Stazed:

This function's sole purpose was to prevent inner_stop() from being called internally when JACK was running... potentially twice. inner_stop() was called by output_func() when JACK sent a JackTransportStopped message. If seg42 initiated the stop, then stop_jack() was called which then triggered the JackTransportStopped message to output_func() which then triggered the bool stop_jack to call inner_stop(). The output_func() call to inner_stop() is only necessary when some other JACK client sends a jack_transport_stop message to JACK, not when it is initiated by seq42. The method of relying on JACK to call inner_stop() when internally initiated caused a (very) obscure apparent freeze if you press and hold the start/stop key if set to toggle. This occurs because of the delay between JackTransportStarting and JackTransportStopped if both triggered in rapid succession by holding the toggle key down. The variable global_is_running gets set false by a delayed inner_stop() from JACK after the start (true) is already sent. This means the global is set to true when JACK is actually off (false). Any subsequent presses to the toggle key send a stop message because the global is set to true. Because JACK is not running, output_func() is not running to send the inner_stop() call which resets the global to false. Thus an apparent freeze as the toggle key endlessly sends a stop, but inner_stop() never gets called to reset. Whoo! So, to fix this we just need to call inner_stop() directly rather than wait for JACK to send a delayed stop, only when running. This makes the whole purpose of this stop() function unneeded. The check for m_jack_running is commented out and this function could be removed. It is being left for future generations to ponder!!!

12.51.4.172 start_jack()

```
void seq64::perform::start_jack ( ) [inline], [private]

12.51.4.173  stop_jack()

void seq64::perform::stop_jack ( ) [inline], [private]

12.51.4.174  position_jack()
```

midipulse tick = 0) [private]

songmode	If true, playback is to be in Song mode. Otherwise, it is to be in Live mode.
tick	Provides the pulse position to be set. The default value is 0.

12.51.4.175 off_sequences()

```
void seq64::perform::off_sequences ( ) [private]

12.51.4.176 all_notes_off()

void seq64::perform::all_notes_off ( ) [private]
```

Then flush the master MIDI buss.

12.51.4.177 set_active()

If setting it active, the sequence::number() setter is called. It won't modify the sequence's internal copy of the sequence number if it has already been set.

Parameters

seq	Provides the prospective sequence number.
active	True if the sequence is to be set to the active state.

12.51.4.178 set_was_active()

Why do we need this routine?

Parameters

12.51.4.179 reset_sequences()

Note that these calls are folded into one member function of the sequence class. Finally, flush the master MIDI buss.

ı		_							- 1
П	201100	Trv	to provent	notoo from	linaarina	00 00110	o if true	By default, it is false.	- 1
П	Dause	111	to brevent	notes non	riinaenna	on baus	e II II ue.	DV UEIAUII. II IS IAISE.	- 1

12.51.4.180 play()

Starts the playing of all the patterns/sequences.

This function just runs down the list of sequences and has them dump their events. It skips sequences that have no playable MIDI events.

Note how often the "s" (sequence) pointer was used. It was worth offloading all these calls to a new sequence function. Hence the new sequence::play_queue function.

Parameters

tick Provides the tick at which to start playing.

12.51.4.181 set_orig_ticks()

This is really the "last tick" value, so we renamed sequence::set_orig_tick() to sequence::set_last_tick().

Parameters

tick Provides the last-tick value to be set for each sequence that is active.

12.51.4.182 set_beats_per_minute()

Replaces perform::set_bpm() from seq24.

The value is set only if neither JACK nor this performance object are running.

It's not clear that we need to set the "is modified" flag just because we changed the beats per minute. This setting does get saved to the MIDI file, with the c_bpmtag.

Parameters

bpm Provides the beats/minute value to be set. It is clamped, if necessary, between the values SEQ64_MINIMUM_BPM to SEQ64_MAXIMUM_BPM. They provide a wide range of speeds, well beyond what normal music needs.

12.51.4.183 set_looping()

```
void seq64::perform::set_looping (
```

```
bool looping ) [inline], [private]
```

looping The boolean value to set for looping, used in the performance editor.

12.51.4.184 max_active_set()

```
int seq64::perform::max_active_set ( ) const [private]
```

Returns

Returns the value of the highest active set. A value of 0 represents the first set. If no sequences are active, then -1 is returned.

12.51.4.185 launch_input_thread()

```
void seq64::perform::launch_input_thread ( ) [private]
```

This might be a good candidate for a small thread class derived from a small base class.

12.51.4.186 launch_output_thread()

```
void seq64::perform::launch_output_thread ( ) [private]
```

This might be a good candidate for a small thread class derived from a small base class.

12.51.4.187 init_jack()

```
bool seq64::perform::init_jack ( ) [inline], [private]
```

Who calls this routine? The main() routine of the application [via launch()], and the options module, when the Connect button is pressed.

Returns

Returns the result of the init() call; true if JACK sync is now running. If JACK support is not built into the application, then this function returns false, to indicate that JACK is (definitely) not running.

12.51.4.188 deinit_jack()

```
bool seq64::perform::deinit_jack ( ) [inline], [private]
```

Called by launch() and in the options module, when the Disconnect button is pressed.

Returns

Returns the result of the init() call; false if JACK sync is now no longer running. If JACK support is not built into the application, then this function returns true, to indicate that JACK is (definitely) not running.

12.51.4.189 seq_in_playing_screen()

seq Provides the index of the desired sequence.

Returns

Returns true if the sequence adheres to the conditions noted above.

Parameters

flag The value of the modified flag to be set.

12.51.4.191 valid_midi_control_seq()

We were checking against c_midi_track_ctrl as well, but that was a bug. This function is meant to check that the supplied sequence number does not exceed the value of c_midi_controls (32 * 2 + 10 = 74). The track (sequence or pattern) controls rangoe from 0 to 64. Next come the "c_midi_control" values: bpm_up, bpm_dn, ..., play_ss, and, lastly, c_midi_controls itself.

Parameters

seq The sequence number value that should be inside the c_midi_controls range.

Returns

Returns true if the sequence number is valid for accessing the MIDI control values. For this function, no error print-out is generated.

12.51.4.192 is_screenset_valid()

Returns

Returns true if the parameter is valid. For this function, no error print-out is generated.

12.51.4.193 set_running()

```
void seq64::perform::set_running (
                bool running ) [inline], [private]
```

Parameters

```
12.51.4.194 is_pattern_playing() [2/2]
```

12.51.4.195 set_playback_mode()

Parameters

playbackmode The value of the playback mode flag to be set.

12.51.4.196 mute_group_offset()

Parameters

track The number of the desired track.

12.51.4.197 is_seq_valid()

Also see the function is_mseq_valid(), which also checks the pointer stored in the m_seq[] array.

We considered checking the *seq* param against sequence_count(), but this function is called while creating sequences that add to that count, so we continue checking against the "container" size. Also, it is possible to have holes in the array representing inactive sequences, so that sequencer_count() would be too limiting.

sea	The sequencer number, in interval [0, m_sequence_max).

Returns

Returns true if the sequence number is valid.

12.51.4.198 is_mseq_valid()

It also evaluates the m_seq[seq] pointer value.

Note

Since we can have holes in the sequence array, where there are inactive sequences, we check if the sequence is even active before emitting a message about a null pointer for the sequence. We only want to see messages that indicate actual problems.

Parameters

seq

Provides the sequence number to be checked. It is checked for validity. We cannot compare the sequence number versus the sequence_count(), because the current implementation can have inactive holes (with null pointers) interspersed with active pointers.

Returns

Returns true if the sequence number is valid as per is_seq_valid(), and the sequence pointer is not null.

12.51.4.199 install_sequence()

It is common code and using it prevents inconsistences. It assumes values have already been checked. It does not set the "is modified" flag, since adding a sequence by loading a MIDI file should not set it. Compare new_\circ sequence(), used by mainwid and seqmenu, with add_sequence(), used by midifile.

seq	The pointer to the pattern/sequence to add.	
seqnum	The sequence number of the pattern to be added. Not validated, to save some time.	

Returns

Returns true if a sequence was removed, or the sequence was successfully added. In other words, if a real change in sequence pointers occurred. It is up to the caller to decide if the change warrants setting the "is modified" flag.

12.51.4.200 inner_start()

Then, if not is_running(), the playback mode is set to the given state. If that state is true, call off_sequences(). Set the running status, and signal the condition. Then unlock.

Minor issue:

```
In ALSA mode, restarting the sequence moves the progress bar to the beginning of the sequence, even if just pausing. This is fixed by compiling with SEQ64_PAUSE_SUPPORT, which disables calling off_sequences() when starting playback from the song editor / performance window.
```

Parameters

songmode	Sets the playback mode, and, if true, turns off all of the sequences before setting the is-running]
	condition.	

12.51.4.201 inner_stop()

```
void seq64::perform::inner_stop (
                bool midiclock = false ) [private]
```

Note that we do need to set the running flag to false here, even when JACK is running. Otherwise, JACK starts ping-ponging back and forth between positions under some circumstances.

However, if JACK is running, we do not want to reset the sequences... this causes the progress bar for each sequence to move to near the end of the sequence.

Parameters

```
midiclock If true, indicates that the MIDI clock should be used.
```

12.51.4.202 clamp_track()

Fixed the bug we found, where we checked for track > m_seqs_in_set, instead of using the >= operator.

track	The track value to be checked and rectified as necessary.
-------	---

Returns

Returns the track parameter, clamped between 0 and m_seqs_in_set-1, inclusive.

It is called 32 times, corresponding to the pattern/sequence slots in the Patterns window. It first removes the given key-code from the regular and reverse slot-maps. Then it removes the sequence-slot from the regular and reverse slot-maps. Finally, it adds the sequence-slot with a key value of key-code, and adds the key-code with a value of sequence-slot.

Parameters

keycode	The keycode for which to set the sequence slot.
sequence_slot	The sequence slot to be set.

12.51.4.206 set_key_group()

```
void seq64::perform::set_key_group (
          unsigned int keycode,
          long group_slot ) [inline], [private]
```

It is called 32 times, corresponding the pattern/sequence slots in the Patterns window. Compare it to the set_key ← _events() function.

keycode	The keycode for which to set the group slot.
group_slot	The group slot to be set.

12.51.5 Friends And Related Function Documentation

```
12.51.5.1 jack_assistant
friend class jack_assistant [friend]
12.51.5.2 keybindentry
friend class keybindentry [friend]
12.51.5.3 mainwnd
friend class mainwnd [friend]
12.51.5.4 midifile
friend class midifile [friend]
12.51.5.5 optionsfile
friend class optionsfile [friend]
12.51.5.6 options
friend class options [friend]
12.51.5.7 perfedit
friend class perfedit [friend]
12.51.5.8 perfroll
friend class perfroll [friend]
12.51.5.9 input_thread_func
void* input_thread_func (
             void * myperf ) [friend]
```

myperf	Provides the perform object instance that is to be used. Its output_func() is called. Currently, this	
	parameter is not validated, for speed.	

Returns

Always returns nullptr.

12.51.5.10 output_thread_func

Set up the performance, set the process to realtime privileges, and then start the output function.

Parameters

myperf	Provides the perform object instance that is to be used. Its output_func() is called. Currently, this
	parameter is not validated, for speed.

Returns

Always returns nullptr.

12.51.5.11 jack_sync_callback

This JACK synchronization callback informs the specified perform object of the current state and parameters of JACK.

The transport state will be:

- JackTransportStopped when a new position is requested.
- JackTransportStarting when the transport is waiting to start.
- JackTransportRolling when the timeout has expired, and the position is now a moving target.

This is the slow-sync callback, which the stazed code replaces with jack_process_callback().

state	The JACK Transport state.
pos	The JACK position value.
arg	The pointer to the jack_assistant object. Currently not checked for nullity, nor dynamic-casted.

Returns

Returns 1 if the function works, and 0 if something was wrong.

12.51.5.12 jack_process_callback

```
int jack_process_callback (
          jack_nframes_t nframes,
          void * arg ) [friend]
```

12.51.5.13 jack_shutdown

12.51.5.14 jack_timebase_callback

```
void jack_timebase_callback (
          jack_transport_state_t state,
          jack_nframes_t nframes,
          jack_position_t * pos,
          int new_pos,
          void * arg ) [friend]
```

The original version of the function worked properly with Hydrogen, but not with Klick. The new code seems to work with both. More testing and clarification is needed. This new code was "discovered" in the source-code for the "SooperLooper" project:

```
http://essej.net/sooperlooper/
```

The first difference with the new code is that it handles the case where the JACK position is moved (new_pos == true). If this is true, and the JackPositionBBT bit is off in pos->valid, then the new BBT value is set.

The seconds set of differences are in the "else" clause. In the new code, it is very simple: calculate the new tick value, back it off by the number of ticks in a beat, and perhaps go to the first beat of the next bar.

In the old code (complex!), the simple BBT adjustment is always made. This changes (perhaps) the beats_per_bar, beat_type, etc. We need to make these settings use the actual global values for beats set for Sequencer64. Then, if transitioning from JackTransportStarting to JackTransportRolling (instead of checking new_pos!), the BBT values (bar, beat, and tick) are finally adjusted. Here are the steps, with old and new steps noted:

```
-# Calculate the "delta" ticks based on the current frame, the
    ticks_per_beat, the beats_per_minute, and the frame_rate. The old
    code saves this in a local, the new code assigns it to pos->tick.
-# Old code: save this delta as a positive value.
-# Figure out the settings and modify bar, beat, tick, and
    bar_start_tick. The old and new code seem to have the same intent,
    but it seems like the new code is faster and also correct.
- Old code: Calculations are made by division and mod
        operations.
- New code: Calculations are made by increments and decrements
    in a while loop.
```

Stazed:

The call to jack_timebase_callback() to supply JACK with BBT, etc. would occasionally fail when the pos information had zero or some garbage in the pos.frame_rate variable. This would occur when there was a rapid change of frame position by another client... i.e. qjackctl. From the JACK API:

pos address of the position structure for the next cycle; pos->frame will be its frame number. If new_pos is FALSE, this structure contains extended position information from the current cycle. If TRUE, it contains whatever was set by the requester. The timebase_callback's task is to update the extended information here."

The "If TRUE" line seems to be the issue. It seems that qjackctl does not always set pos.frame_rate so we get garbage and some strange BBT calculations that display in qjackctl. So we need to set it here and just use m_jack_frame_rate for calculations instead of pos.frame_rate.

Parameters

state	Indicates the current state of JACK transport.
nframes	The number of JACK frames in the current time period.
pos	Provides the position structure to be filled in, the address of the position structure for the next cycle; pos->frame will be its frame number. If new_pos is FALSE, this structure contains extended position information from the current cycle. If TRUE, it contains whatever was set by the requester. The timebase_callback's task is to update the extended information here.
new_pos	TRUE (non-zero) for a newly requested pos, or for the first cycle after the timebase_callback is defined. This is usually 0 in Sequencer64 at present, and 1 if one, say, presses "rewind" in qjackctl.
arg	Provides the jack_assistant pointer, currently unchecked for nullity.

12.51.5.15 get_current_jack_position

12.51.6 Field Documentation

12.51.6.1 sm_mc_dummy

```
midi_control seq64::perform::sm_mc_dummy [static], [private]
```

Instantiate the dummy midi control object, which is used in lieu of a null pointer.

We're taking code that basically works already, in the sense that it never seems to access a null pointer. So we're not even risking data transfers between this dummy object and the ones we really want to use.

However, it would be nice to be able to detect any errors that occur. How?

12.51.6.2 m_song_start_mode

```
bool seq64::perform::m_song_start_mode [private]
```

This is a replacement for the global setting, but is essentially a global setting itself, and is saved to and restored from the "rc" configuration file. Sometimes called "JACK start mode", it used to be a JACK setting, but now applies to any playback. Do not confuse this setting with m_playback_mode, which has a similar meaning but is more transitory. Probably, the concept needs some clean-up.

```
12.51.6.3 m_start_from_perfedit
bool seq64::perform::m_start_from_perfedit [private]

12.51.6.4 m_reposition
bool seq64::perform::m_reposition [private]

12.51.6.5 m_excell_FF_RW

float seq64::perform::m_excell_FF_RW [private]

12.51.6.6 m_FF_RW_button_type

ff_rw_button_t seq64::perform::m_FF_RW_button_type [private]

12.51.6.7 m_gui_support

gui_assistant& seq64::perform::m_gui_support [private]

12.51.6.8 m_mute_group

bool seq64::perform::m_mute_group[c_max_sequence] [private]
```

This value determines whether a particular track will be muted or unmuted, and it can handle all tracks available in the application (currently c_max_sets * c_seqs_in_set, i.e. 1024). Note that the current state of playing can be "learned", and stored herein as the desired state for the track.

```
12.51.6.9 m_armed_saved
bool seq64::perform::m_armed_saved [private]

12.51.6.10 m_armed_statuses

bool seq64::perform::m_armed_statuses[c_max_sequence] [private]

12.51.6.11 m_tracks_mute_state

bool seq64::perform::m_tracks_mute_state[c_seqs_in_set] [private]
```

Unlike the m_mute_group[] array, this holds the current state, rather than the state desired by activating a mute group, and it applies to only one screen-set.

12.51.6.12 m_mode_group

```
bool seq64::perform::m_mode_group [private]
```

This value starts out true. It is altered by the c_midi_control_mod_gmute handler or when the keys().group_off() or the keys().group_on() keys are struck.

12.51.6.13 m_mode_group_learn

```
bool seq64::perform::m_mode_group_learn [private]
```

12.51.6.14 m_mute_group_selected

```
int seq64::perform::m_mute_group_selected [private]
```

It seems like a "group" is essentially a "set" that is selected for the saving and restoring of the status of all patterns in that set.

12.51.6.15 m_playing_screen

```
int seq64::perform::m_playing_screen [private]
```

In seq24, this value is altered by set_playing_screenset(), which is called by handle_midi_control(c_midi_control ← _play_ss, state).

12.51.6.16 m_playscreen_offset

```
int seq64::perform::m_playscreen_offset [private]
```

Saves some multiplications, should make the code easier to grok, and centralizes the use of c_seqs_in_set, which we want to be able to change at run-time, as a future enhancement.

12.51.6.17 m_seqs

```
sequence* seq64::perform::m_seqs[c_max_sequence] [private]
```

Todo First, make the sequence array a vector, and second, put allof these flags into a structure and access those members indirectly.

12.51.6.18 m_seqs_active

```
bool seq64::perform::m_seqs_active[c_max_sequence] [private]
```

This array can have "holes" with inactive sequences, so every sequence needs to be checked before using it.

12.51.6.19 m_was_active_main

```
bool seq64::perform::m_was_active_main[c_max_sequence] [private]
```

This value seems to be used only in maintaining dirtiness-status; did some process modify the sequence? Was it's mute/unmute status changed?

12.51.6.20 m was active edit

```
bool seq64::perform::m_was_active_edit[c_max_sequence] [private]
```

This value seems to be used only in maintaining dirtiness-status for editing the mute/unmute status during pattern editing.

12.51.6.21 m_was_active_perf

```
bool seq64::perform::m_was_active_perf[c_max_sequence] [private]
```

This value seems to be used only in maintaining dirtiness-status for editing the mute/unmute status during performance/song editing.

12.51.6.22 m_was_active_names

```
bool seq64::perform::m_was_active_names[c_max_sequence] [private]
```

This value seems to be used only in maintaining dirtiness-status for editing the mute/unmute status during performance names editing. Not sure that it serves a real purpose; perhaps created with an eye to editing the pattern name in the song editor?

12.51.6.23 m_sequence_state

```
bool seq64::perform::m_sequence_state[c_max_sequence] [private]
```

12.51.6.24 m_master_bus

```
mastermidibus seq64::perform::m_master_bus [private]
```

12.51.6.25 m_transpose

```
int seq64::perform::m_transpose [private]
```

12.51.6.26 m_out_thread

```
pthread_t seq64::perform::m_out_thread [private]
```

Provides a "handle" to the output thread.

12.51.6.27 m_in_thread

```
pthread_t seq64::perform::m_in_thread [private]
```

12.51.6.28 m_out_thread_launched

```
bool seq64::perform::m_out_thread_launched [private]
```

12.51.6.29 m_in_thread_launched

```
bool seq64::perform::m_in_thread_launched [private]
```

12.51.6.30 m_running

```
bool seq64::perform::m_running [private]
```

However, this flag is conflated with some JACK support, and we have to supplement it with another flag, m_← pattern_playing.

12.51.6.31 m_is_pattern_playing

```
bool seq64::perform::m_is_pattern_playing [private]
```

It replaces rc_settings :: is_pattern_playing(), which is gone, since the perform object is now visible to all classes that care about it.

12.51.6.32 m_inputing

```
bool seq64::perform::m_inputing [private]
```

12.51.6.33 m_outputing

bool seq64::perform::m_outputing [private]

12.51.6.34 m_looping

```
bool seq64::perform::m_looping [private]
```

If true, the performance will loop between the L and R markers in the performance editor.

```
12.51.6.35 m_playback_mode
```

```
bool seq64::perform::m_playback_mode [private]
```

There are two, "live" and "song", indicated by the following values:

```
m_playback_mode == false: live mode
m_playback_mode == true: playback/song mode
```

12.51.6.36 m_ppqn

```
int seq64::perform::m_ppqn [private]
```

12.51.6.37 m beats per bar

```
int seq64::perform::m_beats_per_bar [private]
```

The default value is SEQ64_DEFAULT_BEATS_PER_MEASURE (4).

12.51.6.38 m beat width

```
int seq64::perform::m_beat_width [private]
```

The default value is SEQ64_DEFAULT_BEAT_WIDTH (4).

12.51.6.39 m_clocks_per_metronome

```
int seq64::perform::m_clocks_per_metronome [private]
```

This value provides the number of MIDI clocks between metronome clicks. The default value of this item is 24. It can also be read from some SMF 1 files, such as our hymne.mid example.

12.51.6.40 m_32nds_per_quarter

```
int seq64::perform::m_32nds_per_quarter [private]
```

Useful in export. A duplicate of the same member in the sequence class.

12.51.6.41 m_us_per_quarter_note

```
long seq64::perform::m_us_per_quarter_note [private]
```

Useful in export. A duplicate of the same member in the sequence class.

```
12.51.6.42 m_one_measure
```

```
midipulse seq64::perform::m_one_measure [private]
```

We can save some multiplications, and, more importantly, later define a more flexible definition of "one measure's worth" than simply four quarter notes.

```
12.51.6.43 m left tick
```

```
midipulse seq64::perform::m_left_tick [private]
```

Note that "tick" is actually "pulses".

```
12.51.6.44 m_right_tick
```

```
midipulse seq64::perform::m_right_tick [private]
```

Note that "tick" is actually "pulses".

12.51.6.45 m_starting_tick

```
midipulse seq64::perform::m_starting_tick [private]
```

By default, this value is always reset to the value of the "left tick". We want to eventually be able to leave it at the last playing tick, to support a "pause" functionality. Note that "tick" is actually "pulses".

```
12.51.6.46 m_tick
```

```
midipulse seq64::perform::m_tick [mutable], [private]
```

The m_tick member holds the tick to be used in displaying the progress bars and the maintime pill. It is mutable because sometimes we want to adjust it in a const function for pause functionality.

```
12.51.6.47 m_jack_tick
```

```
midipulse seq64::perform::m_jack_tick [private]
```

12.51.6.48 m_usemidiclock

```
bool seq64::perform::m_usemidiclock [private]
```

12.51.6.49 m_midiclockrunning

```
bool seq64::perform::m_midiclockrunning [private]
```

```
12.51.6.50 m_midiclocktick
int seq64::perform::m_midiclocktick [private]
12.51.6.51 m_midiclockpos
int seq64::perform::m_midiclockpos [private]
12.51.6.52 m_dont_reset_ticks
bool seq64::perform::m_dont_reset_ticks [private]
All this member is used for is keeping the last tick from being reset.
12.51.6.53 m_screen_set_notepad
std::string seq64::perform::m_screen_set_notepad[c_max_sets] [private]
12.51.6.54 m_midi_cc_toggle
midi_control seq64::perform::m_midi_cc_toggle[c_midi_controls] [private]
12.51.6.55 m midi cc on
midi_control seq64::perform::m_midi_cc_on[c_midi_controls] [private]
12.51.6.56 m_midi_cc_off
midi_control seq64::perform::m_midi_cc_off[c_midi_controls] [private]
12.51.6.57 m_offset
```

It is used in the MIDI control of the playback status of the sequences in the current screen-set. It is also used to offset the sequence numbers so that the control (mute/unmute) keys can be shown on any screen-set.

```
12.51.6.58 m_control_status
int seq64::perform::m_control_status [private]
```

int seq64::perform::m_offset [private]

Need to learn more about this one. It is used in the replace, snapshot, and queue functionality.

12.51.6.59 m_screenset

```
int seq64::perform::m_screenset [private]
```

This is merely the screen-set that is in view. The fix of tdeagan substitutes the "in-view" screen-set for the "playing" screen-set.

12.51.6.60 m_seqs_in_set

```
int seq64::perform::m_seqs_in_set [private]
```

This change will require some arrays to be dynamically allocated (vectors).

12.51.6.61 m_max_sets

```
int seq64::perform::m_max_sets [private]
```

Again, currently set to the old value, which is used in hard-wired array sizes. To make it variable will require a move from arrays to vectors.

12.51.6.62 m_sequence_count

```
int seq64::perform::m_sequence_count [private]
```

Used by the install_sequence() function. Note that this value is not a suitable replacement for c_max_sequence/m← _sequence_max, because there can be inactive sequences amidst the active sequences.

12.51.6.63 m_sequence_max

```
int seq64::perform::m_sequence_max [private]
```

However, this value is already 32 * 32 = 1024, and is probably enough for any usage. Famous last words?

12.51.6.64 m_edit_sequence

```
int seq64::perform::m_edit_sequence [private]
```

Moving this status from seqmenu into perform for better centralized management.

12.51.6.65 m_is_modified

```
bool seq64::perform::m_is_modified [private]
```

All the GUIs seem to use a perform object.

```
12.51.6.66 m_condition_var
```

```
condition_var seq64::perform::m_condition_var [private]
```

It is signalled if playback has been started. The output thread function waits on this variable until m_running and m_outputing are false. This variable is also signalled in the perform destructor.


```
12.51.6.67 m_jack_asst
jack_assistant seq64::perform::m_jack_asst [private]
It implements most of the JACK stuff.
12.51.6.68 m_have_undo
bool seq64::perform::m_have_undo [private]
12.51.6.69 m_undo_vect
std::vector<int> seq64::perform::m_undo_vect [private]
12.51.6.70 m_have_redo
bool seq64::perform::m_have_redo [private]
12.51.6.71 m_redo_vect
std::vector<int> seq64::perform::m_redo_vect [private]
12.51.6.72 m_notify
```

std::vector<performcallback *> seq64::perform::m_notify [private]

12.52 seq64::performcallback Struct Reference

Provides for notification of events.

Inheritance diagram for seq64::performcallback:



Public Member Functions

virtual void on_grouplearnchange (bool)

A do-nothing callback.

12.52.1	Detailed D	escription
16.06.1	Detailed D	CSCHDUION

Provide a response to a group-learn change event.

12.52.2 Member Function Documentation

12.52.2.1 on_grouplearnchange()


"state" is an Unused parameter.

Reimplemented in seq64::mainwnd.

12.53 seq64::perfroll Class Reference

This class implements the performance roll user interface.

Inheritance diagram for seq64::perfroll:



Public Member Functions

• perfroll (perform &perf, perfedit &parent, Gtk::Adjustment &hadjust, Gtk::Adjustment &vadjust, int ppqn=S ← EQ64_USE_DEFAULT_PPQN)

Principal constructor.

virtual ∼perfroll ()

This destructor deletes the interaction object.

· void set_guides (int snap, int measure, int beat)

This function sets the m_snap, m_measure_length, and m_beat_length members directly from the function parameters, which are in units of pulses (sometimes misleadingly called "ticks".)

· void update sizes ()

Updates the sizes of various items.

void init_before_show ()

Sets the roll-lengths ticks member.

void fill_background_pixmap ()

This function updates the background of the piano roll.

void increment_size ()

Increments the value of m_roll_length_ticks by the PPQN * 512, then calls update_sizes().

• void draw all ()

Provides a very common sequence of calls used in perfroll_input.

- void follow_progress ()
- void redraw_progress ()

Helper function to simplify the client call.

Private Member Functions

void draw_progress ()

Draws the progress line that shows where we are in the performance.

void redraw_dirty_sequences ()

Redraws patterns/sequences that have been modified.

void set_ppqn (int ppqn)

Handles changes to the PPQN value in one place.

void convert_xy (int x, int y, midipulse &ticks, int &seq)

Converts (x, y) coordinates on the piano roll to tick (pulse) and sequence numbers.

void convert_x (int x, midipulse &ticks)

Converts an x-coordinate to a tick-offset on the x axis.

void snap x (int &x)

This function performs a 'snap' action on x.

void draw_sequence_on (int seqnum)

Draws the given pattern/sequence on the given drawable area.

void draw_background_on (int seqnum)

Draws the given pattern/sequence background on the given drawable area.

void draw_drawable_row (long y)

Not quite sure what this draws yet.

• void change horz ()

Changes the 4-bar horizontal offset member and queues up a draw operation.

• void change_vert ()

Changes the vertical offset member and queues up a draw operation.

void split_trigger (int sequence, midipulse tick)

Splits a trigger, whatever that means.

• void enqueue draw ()

Wraps queue_draw() and forwards the call to the parent perfedit, so that it can forward it to any other perfedit that exists.

• void set_zoom (int z)

Implements the horizontal zoom feature.

void convert_drop_xy ()

A convenience function.

void horizontal_adjust (double step)

This function provides optimization for the on_scroll_event() function.

· void vertical adjust (double step)

This function provides optimization for the on_scroll_event() function.

void horizontal_set (double value)

Sets the exact position of a horizontal scroll-bar.

· void vertical_set (double value)

Sets the exact position of a vertical scroll-bar.

void on_realize ()

Provides the on-realization callback.

bool on expose event (GdkEventExpose *ev)

Handles the on-expose event.

bool on_button_press_event (GdkEventButton *ev)

This callback function handles a button press by forwarding it to the interaction object's button-press function.

bool on button release event (GdkEventButton *ev)

This callback function handles a button release by forwarding it to the interaction object's button-release function.

bool on_motion_notify_event (GdkEventMotion *ev)

Handles motion notification by forwarding it to the interaction object's motion-notification callback function.

bool on scroll event (GdkEventScroll *ev)

Handles horizontal and vertical scrolling.

bool on_focus_in_event (GdkEventFocus *ev)

This callback handles an in-focus event by setting the flag to HAS_FOCUS.

bool on_focus_out_event (GdkEventFocus *ev)

This callback handles an out-of-focus event by resetting the flag HAS_FOCUS.

• void on_size_allocate (Gtk::Allocation &al)

Upon a size allocation event, this callback calls the base-class version of this function, then sets m_window_x and m_window_y, and calls update_sizes().

bool on_key_press_event (GdkEventKey *ev)

This callback function handles a key-press event.

void on size request (GtkRequisition *)

This do-nothing callback effectively throws away a size request.

Private Attributes

· perfedit & m parent

Provides a link to the perfedit that created this object.

· int m_h_page_increment

Provides the horizontal page increment for the horizontal scrollbar.

int m_v_page_increment

Provides the vertical page increment for the vertical scrollbar.

• int m_snap

The amount of horizontal snap.

• int m_ppqn

Parts-per-quarter-note value.

int m_page_factor

4096, horizonal page sizing.

· int m divs per beat

Holds current tick scaling value.

· midipulse m ticks per bar

Holds current bar scaling value.

• int m_perf_scale_x

Scaling based on zoom and PPQN.

• int m zoom

New value to attempt a rudimentary time-zoom feature.

int m_names_y

The maximum height of the perfroll names box, in pixes.

int m background x

The width of the perfroll background.

· int m_size_box_w

This is a basically constant value set to s perfroll size box w = 3.

· int m measure length

The legnth of a measure, in beat units.

· int m_beat_length

The length of a beat, in parts-per-quarter note.

· midipulse m old progress ticks

Saves the position of the progress bar, for erasing it in preparation for drawing it at the next tick value.

· bool m have button press

Used in the fruity and seq24 perfroll input classes to help with trigger push/pop management.

· bool m transport follow

Indicates that the application should follow JACK transport.

• bool m_trans_button_press

Indicates if the follow-transport button is pressed.

· midipulse m 4bar offset

Holds the horizontal offset related to the horizontal scroll-bar position.

int m_sequence_offset

This value is the vertical version of m_4bar_offset.

int m_roll_length_ticks

Provides the width of the piano roll in ticks.

• midipulse m_drop_tick

The horizontal location for section movement.

midipulse m_drop_tick_trigger_offset

The horizontal trigger location for section movement.

int m_drop_sequence

Holds the currently-selected sequence being moved.

· int m sequence max

Currently, just a class-specific version of c_max_sequence, meant for the future.

• bool m_sequence_active [c_max_sequence]

Used when drawing an active sequence.

• FruityPerfInput m_fruity_interaction

We need both styles of interaction object present.

• Seq24PerfInput m_seq24_interaction

Provides support for standard Seq24 mouse handling, plus the keystroke handlers.

• AbstractPerfInput & m_interaction

Provides a reference to the selected (at startup time) method of mouse interaction.

bool m_moving

Used in the Seq24 or Fruity processing when moving a section of triggers.

• bool m_growing

Used in the Seq24 or Fruity processing when growing a section of triggers.

bool m_grow_direction

Used in the Seq24 or Fruity processing when growing a section of triggers.

Friends

class FruityPerfInput

These friend implement interaction-specific behavior, although only the Seq24 interactions support full keyboard processing, except for some common functionality provided by perform::perfroll_key_event().

- class Seq24PerfInput
- · class perfedit

Additional Inherited Members

12.53.1 Constructor & Destructor Documentation

12.53.1.1 perfroll()

Well, now there are two objects, so no explicit deletion necessary.

12.53.2 Member Function Documentation

12.53.2.1 set_guides()

This function then fills in the background, and queues up a draw operation.

Parameters

snap	Provides the number of snap-pulses (pulses per snap interval) as calculated in <pre>perfedit::set_guides()</pre> . This is actually equal to the measure-pulses divided by the snap value in <pre>perfedit</pre> ; the snap value defaults to 8.	
measure	Provides the number of measure-pulses (pulses per measure) as calculated in perfedit::set_guides().	
beat	Provides the number of beat-pulses (pulses per beat) as calculated in perfedit::set_guides().	

12.53.2.2 update_sizes()

```
void seq64::perfroll::update_sizes ( )
```

Note

Trying to figure out what the 16 is. So take the "bars-visible" calculation, the c_perf_scale_x value, assume that "ticks" is another name for "pulses", and assume that "beats" is a quarter note. Ignoring the numbers, the units come out to:

```
pixels * ticks / pixel
bars = -----
ticks / beat * beats / bar

Thus, the 16 is a "beats per bar" or "beats per measure" value.
```

This doesn't quite make sense, but there are 16 divisions per beat on the perfroll user-interface. So for now we'll call it the latter, and make a variable called "m_divs_per_beat", see its definition in the class initializer list.

12.53.2.3 init_before_show()

```
void seq64::perfroll::init_before_show ( )
```

First, it gets the largest trigger value among the active sequences. Then it truncates this value to the nearest PPQN * 16 ticks. Then it adds PPQN * 4096 ticks.

12.53.2.4 fill_background_pixmap()

```
void seq64::perfroll::fill_background_pixmap ( )
```

The first thing done is to clear the background by painting it with a filled white rectangle.

This function is called whenever something occurs (e.g. zoom) that can affect how the piano roll is drawn.

12.53.2.5 increment_size()

```
void seq64::perfroll::increment_size ( )
12.53.2.6 draw_all()
```

```
void seq64::perfroll::draw_all ( )
```

m_drop_y is adjusted by perfroll::change_vert() for any scroll after it was originally selected. The call below to draw_drawable_row() will have the wrong y location and un-select will not occur if the user scrolls the track up or down to a new y location, if not adjusted.

12.53.2.7 follow_progress()

```
void seq64::perfroll::follow_progress ( )
```

```
12.53.2.8 redraw_progress()
void seq64::perfroll::redraw_progress ( ) [inline]

12.53.2.9 draw_progress()
void seq64::perfroll::draw_progress ( ) [private]
```

We would like to be able to leave the line there when the progress is paused while running off of JACK transport. How? The perf().get_tick() call always returns 0 when stop is in force.

If we comment out the erasure of the old line, we see that the progress bar is also erased when a pattern boundary is hit (triggers), and when the sequence is stopped by the user.

In order to support true pause in the song editor, we tried to replace perform::get_tick() with perform::get_start_tick() and perform::get_last_tick() [a new experimental function]. But those replacements here always return 0, even as perform::get_tick() increases. Now were are trying a newer function, perform::get_max_tick(), which seems to do the trick for resuming (instead of rewinding) the progress bar. It's still a tiny bit laggy, so we have to find a faster way to get the maximum. (Note that the draw progress function is called at every timeout, that is, constantly.)

The perform::get_max_tick() call doesn't work with JACK: the progress bar rewinds to the beginning when playback is paused, though it does resume where it left off. It also may cause the progress bar to backtrack through any gap. Let's restore the get_tick() call.

```
12.53.2.10 redraw_dirty_sequences()
void seq64::perfroll::redraw_dirty_sequences ( ) [private]
```

Change Note ca 2016-05-30 Lets try not drawing sequences greater than the maximum, at all.

The m_ticks_per_bar member replaces the global ppqn times 16. This construct is parts-per-quarter-note times 4 quarter notes times 4 sixteenth notes in a bar. (We think...)

The m_perf_scale_x member starts out at c_perf_scale_x, which is 32 ticks per pixel at the default tick rate of 192 PPQN. We adjust this now. But note that this calculation still involves the c_perf_scale_x constant.

Todo Resolve the issue of c_perf_scale_x versus m_perf_scale_x in perfroll.

12.53.2.12 convert_xy()

The results are returned via the d_tick and d_seq parameters. The sequence number is clipped to a legal value (0 to m_sequence_max).

Parameters

	X	The x coordinate of the mouse pointer.	
	У	The y coordinate of the mouse pointer.	
out	d_tick	Holds the calculated tick value.	
out	at d_seq Holds the calculated sequence-number value.		

12.53.2.13 convert_x()

```
void seq64::perfroll::convert_x (
          int x,
          midipulse & tick ) [private]
```

The result is returned via the tick parameter. Note that m_4bar_offset already includes the m_ticks_per_bar = ppqn * 16 factor, for speed.

Parameters

	X	The input x (pixel) value.	
out	tick	Holds the result of the calculation.	

12.53.2.14 snap_x()

- m_snap = number pulses to snap to
- m_perf_scale_x = number of pulses per pixel

Therefore $mod = m_snap/m_perf_scale_x$ equals the number pixels to snap to.

12.53.2.15 draw_sequence_on()

Statement nesting from hell!

12.53.2.16 draw_background_on()

```
12.53.2.17 draw_drawable_row()
```

It is involved in the drawing of a greyed (selected) row.

What's weird is that we divide y by m_names_y, then multiply it by m_names_y, before passing the result to draw—drawable(). However, if we just use y casted to an int, then the drawing of the row is only partial, vertically.

```
12.53.2.18 change_horz()
```

```
void seq64::perfroll::change_horz ( ) [private]
```

Since the m_4bar_offset value is always multiplied by m_ticks_per_bar before usage, let's just do it here and not have to multiply it later.

12.53.2.19 change_vert()

```
void seq64::perfroll::change_vert ( ) [private]
```

Stazed:

```
Must adjust m_drop_y or perfroll_input's unselect_triggers() will not work if scrolled up or down to a new location. See the note in on_button_press_event() in the perfroll_input module. Also see the note in the draw_all() function.
```

12.53.2.20 split_trigger()

12.53.2.21 enqueue_draw()

```
void seq64::perfroll::enqueue_draw ( ) [private]
```

The parent perfedit will call perfroll::queue_draw() on behalf of this object, and it will pass a perfroll::enqueue_draw() to the peer perfedit's perfroll, if the peer exists.

12.53.2.22 set_zoom()

Change Note ca 2016-04-05 The initial zoom value is c_perf_scale_x (32). We allow it to range from 1 to 128, for now. Smaller values zoom in.

12.53.2.23 convert_drop_xy()

```
void seq64::perfroll::convert_drop_xy ( ) [inline], [private]
```

12.53.2.24 horizontal_adjust()

A duplicate of the one in seqroll.

Parameters

step

Provides the step value to use for adjusting the horizontal scrollbar. See gui_drawingarea_gtk2::scroll_hadjust() for more information.

12.53.2.25 vertical_adjust()

A near-duplicate of the one in seqroll.

Parameters

step

Provides the step value to use for adjusting the vertical scrollbar. See gui drawingarea gtk2::scroll vadjust() for more information.

12.53.2.26 horizontal_set()

Parameters

value

The desired position. Mostly this is either 0.0 or 9999999.0 (an "infinite" value to select the start or end position.

12.53.2.27 vertical_set()

Parameters

value

The desired position. Mostly this is either 0.0 or 9999999.0 (an "infinite" value to select the start or end position.

12.53.2.28 on_realize()

```
void seq64::perfroll::on_realize ( ) [private]
```

Calls the base-class version first.

Then it allocates the additional resources need, that couldn't be initialized in the constructor, and makes some connections.

Stazed:

This creation of m_background needs to be set to the max width for proper drawing of zoomed measures or they will get truncated with high beats per measure and low beat width. Since this is a constant size, it cannot be adjusted later for zoom. The constant c_perfroll_background_x is set to the max amount by default for use here. The drawing functions fill_background_pixmap() and draw_background_on() which use c_perfroll_background_x also, could be adjusted by zoom with a substituted variable. Not sure if there is any benefit to doing the adjustment... Perhaps a small benefit in speed? Maybe FIXME if really, really bored...

12.53.2.29 on_expose_event()

```
bool seq64::perfroll::on_expose_event (
        GdkEventExpose * ev ) [private]
```

Draws a vertical page of the performance editor. The part drawn starts at m_sequence_offset and continues until the last sequence that can be at least partially seen given the height of the window.

If we're at the bottom of the sequences (1024, a non-existent sequence) would be the last sequence shown, we don't bother drawing it. This prevents debug messages about an illegal sequence, and can show a black bottom row that is a clear sign we're at the end of the legal sequences.

Parameters

```
ev Provides the expose event.
```

Returns

Always returns true.

12.53.2.30 on_button_press_event()

```
bool seq64::perfroll::on_button_press_event ( {\tt GdkEventButton} \ *\ ev\ ) \quad [{\tt private}]
```

This gives us Seq24 versus Fruity behavior.

One minor issue: Fruity behavior doesn't yet provide the keystroke behavior we now handle for the Seq24 mode of operation.

12.53.2.31 on_button_release_event()

This gives us Seq24 versus Fruity behavior.

12.53.2.32 on_motion_notify_event()

12.53.2.33 on_scroll_event()

If the Shift key is held while scrolling, then the scrolling is horizontal, otherwise it is vertical. This matches the convention of the seqedit class.

Note that, unlike the sequest class, Ctrl-Scroll is not used to modify the zoom value. Rather than mess up legacy behavior, we will rely on keystrokes (z, 0, Z, and Ctrl-Page-Up and Ctrl-Page-Down) to implement this zoom.

Parameters

```
ev Provides the scroll event.
```

Returns

Currently always returns true.

```
12.53.2.34 on_focus_in_event()
```

If we don't check the event type first, then the ev->keyval value is something weird like 65507. Note that we pass the functionality on to the perform::perfroll_key_event() function for the handling of delete, cut, copy, paste, and undo operations. If the keystroke is not handled by that function, then we handle it here.

Note that only the Seq24 input interaction object handles additional keystrokes not handled by the perfroll_key_ event() function.

The perfroll key event() call handles Del, Ctrl-X, Ctrl-C, Ctrl-V, and Ctrl-Z (which does nothing at present).

We've also added support for moving up and down in the piano roll (Up and Down arrows), paging up and down (Page-Up and Page-Down keys), paging left and right (Shift Page-Up and Page-Down), paging to top and bottom (Home and End), and paging to start and end (Shift Home and End).

The Keypad-End key is an issue on our ASUS "gaming" laptop. Whether it is seen as a "1" or an "End" key depends on an interaction between the Shift and the Num Lock key. Annoying, takes some time to get used to.

Stazed: there are many changes from seq32 that need to be studied before including them here. Note that, even though we filter out the Ctrl key here, it still works for Ctrl-X (cut) and Ctrl-V (paste). For undo, the Undo button can be used, Ctrl-Z never worked in this view anyway.

Warning

We see that 'x' and 'z' are already handled in perfroll_key_event() if the Ctrl key was pressed. Be careful.

12.53.2.38 on_size_request()

12.53.3 Friends And Related Function Documentation

12.53.3.1 FruityPerfInput

```
friend class FruityPerfInput [friend]
```

The perfedit class needs access to the private enqueue_draw() function.

12.53.3.2 Seq24PerfInput

```
friend class Seq24PerfInput [friend]
```

12.53.3.3 perfedit

```
friend class perfedit [friend]
```

12.53.4 Field Documentation

12.53.4.1 m_parent

```
perfedit& seq64::perfroll::m_parent [private]
```

We want to support two perfedit windows, but the children of perfedit will have to communicate changes requiring a redraw through the parent.

12.53.4.2 m_h_page_increment

```
int seq64::perfroll::m_h_page_increment [private]
```

It was set to 1, the same as the step increment. That is too little. This value will be set to 4, for now. Might be a useful "user" configuration option.

12.53.4.3 m_v_page_increment

```
int seq64::perfroll::m_v_page_increment [private]
```

It was set to 1, the same as the step increment. That is too little. This value will be set to 8, for now. Might be a useful "user" configuration option.

```
12.53.4.4 m_snap
int seq64::perfroll::m_snap [private]
12.53.4.5 m_ppqn
int seq64::perfroll::m_ppqn [private]
12.53.4.6 m_page_factor
int seq64::perfroll::m_page_factor [private]
12.53.4.7 m_divs_per_beat
int seq64::perfroll::m_divs_per_beat [private]
12.53.4.8 m_ticks_per_bar
midipulse seq64::perfroll::m_ticks_per_bar [private]
12.53.4.9 m_perf_scale_x
int seq64::perfroll::m_perf_scale_x [private]
12.53.4.10 m_zoom
int seq64::perfroll::m_zoom [private]
It seems to work pretty well now.
12.53.4.11 m_names_y
int seq64::perfroll::m_names_y [private]
This is currently semantically a constant set to c_names_y = 24.
12.53.4.12 m_background_x
int seq64::perfroll::m_background_x [private]
This is based on the m_ppqn value and the value of c_perf_scale_x (or is m_perf_scale_x preferable?)
```

```
12.53.4.13 m_size_box_w
```

```
int seq64::perfroll::m_size_box_w [private]
```

It is used in drawing the short lines of the small box that sits at the top-left and bottom-right corners of each segment in the pattern editor. These can be used to lengthen and shorten a section in the song editor. We will increase this size, perhaps double it, to make it easier to grab.

```
12.53.4.14 m_measure_length
int seq64::perfroll::m_measure_length [private]
12.53.4.15 m_beat_length
int seq64::perfroll::m_beat_length [private]
12.53.4.16 m_old_progress_ticks
midipulse seq64::perfroll::m_old_progress_ticks [private]
See the <a href="mailto:draw_progress">draw_progress</a>() function. This could almost be static inside that function.
12.53.4.17 m_have_button_press
bool seq64::perfroll::m_have_button_press [private]
12.53.4.18 m_transport_follow
bool seq64::perfroll::m_transport_follow [private]
The alternative is ...?
12.53.4.19 m_trans_button_press
bool seq64::perfroll::m_trans_button_press [private]
12.53.4.20 m_4bar_offset
```

midipulse seq64::perfroll::m_4bar_offset [private]

Used in drawing the progress bar and the sequence events. Also used in convert_x() and convert_xy(). This used to be the offset in units of bar ticks, but now we use it as a full-fledged ticks value. See the change_horz() function.

```
12.53.4.21 m_sequence_offset
```

```
int seq64::perfroll::m_sequence_offset [private]
```

It is obtained or changed when the vertical scroll-bar moves. It is used for drawing the correct vertical window in the piano roll.

12.53.4.22 m_roll_length_ticks

```
int seq64::perfroll::m_roll_length_ticks [private]
```

Calculated in init_before_show() based on the maximum trigger found in the perform object, the ticks/bar, the $P \leftarrow PQN$, and the page factor. Also can be increased in size in the increment_size() function [tied to the Grow button]. Used in update_sizes().

12.53.4.23 m_drop_tick

```
midipulse seq64::perfroll::m_drop_tick [private]
```

Used only by the friend modules perfroll input and fruityperfroll input.

12.53.4.24 m_drop_tick_trigger_offset

```
midipulse seq64::perfroll::m_drop_tick_trigger_offset [private]
```

Used only by the friend modules perfroll_input and fruityperfroll_input.

12.53.4.25 m_drop_sequence

```
int seq64::perfroll::m_drop_sequence [private]
```

Used for redrawing the sequence.

12.53.4.26 m_sequence_max

```
int seq64::perfroll::m_sequence_max [private]
```

12.53.4.27 m_sequence_active

```
bool seq64::perfroll::m_sequence_active[c_max_sequence] [private]
```

Not sure yet why we can't just use the sequence's member function to access this status boolean.

```
12.53.4.28 m_fruity_interaction
```

```
FruityPerfInput seq64::perfroll::m_fruity_interaction [private]
```

Even if the user specifies the fruity interaction, the Seq24 interaction is still needed to handle our new keystroke support for the perfroll. We need both objects to exist all the time, similar to the Fruity/Seq24 roles in the seqroll object.

Obsolete AbstractPerfInput * m_interaction

```
12.53.4.29 m_seq24_interaction
```

```
Seq24PerfInput seq64::perfroll::m_seq24_interaction [private]
```

12.53.4.30 m_interaction

```
AbstractPerfInput& seq64::perfroll::m_interaction [private]
```

12.53.4.31 m_moving

```
bool seq64::perfroll::m_moving [private]
```

12.53.4.32 m_growing

```
bool seq64::perfroll::m_growing [private]
```

12.53.4.33 m_grow_direction

```
bool seq64::perfroll::m_grow_direction [private]
```

Determines whether the section is growing to the left or to the right.

12.54 seq64::perftime Class Reference

This class implements drawing the piano time at the top of the "performance window" (the "song editor"). Inheritance diagram for seq64::perftime:



Public Member Functions

• perftime (perform &perf, perfedit &parent, Gtk::Adjustment &hadjust, int ppqn=SEQ64_USE_DEFAULT_P ← PQN)

Principal constructor.

virtual ~perftime ()

Let's provide a do-nothing virtual destructor.

- · void reset ()
- void set scale (int scale)
- void set guides (int snap, int measure)

Sets the m_snap value and the m_measure_length members directly from the function parameters, which are in units of pulses (sometimes misleadingly called "ticks".)

· void increment size ()

This function does nothing.

Private Member Functions

• void enqueue draw ()

Wraps queue_draw() and forwards the call to the parent perfedit, so that it can forward it to any other perfedit that exists.

void set zoom (int z)

Implements the horizontal zoom feature.

void draw_background ()

Separated out the drawing done in on_expose_event(), so that it can be redone when the zoom changes.

- void draw_progress_on_window ()
- void change horz ()

Changes the m_4bar_offset and queues a draw operation.

void set_ppqn (int ppqn)

Handles changes to the PPQN value in one place.

long tick_to_pixel (midipulse tick)

Common calculation to convert a pulse/tick value to a perftime x value.

midipulse pixel_to_tick (long pixel)

The inverse of tick_to_pixel().

· int tick offset ()

Centralizes calculation of the tick offset of the time bar.

• void update_sizes ()

This function does nothing.

• int idle_progress ()

This function just returns true.

• void update_pixmap ()

This function does nothing.

void draw_pixmap_on_window ()

This function does nothing.

void on_realize ()

Implements the on-realization event, then allocates some resources the could not be allocated in the constructor.

bool on expose event (GdkEventExpose *ev)

Implements the on-expose event.

bool on_button_press_event (GdkEventButton *ev)

Implement the button-press event to set the L and R ticks.

• void on_size_allocate (Gtk::Allocation &r)

Implements a size-allocation event.

bool on_button_release_event (GdkEventButton *)

This button-release handler does nothing.

bool key_press_event (GdkEventKey *ev)

This callback function handles a key-press event.

Private Attributes

· perfedit & m_parent

Provides a link to the perfedit that created this object.

· int m_4bar_offset

Not yet sure exactly what this member represents.

· int m_tick_offset

This member is m_4bar_offset times 16 times the current PPQN, to save some calculations and centralize this value.

• int m_ppqn

The current value of PPQN, which we are trying to get to work everywhere, when PPQN is changed from the global ppqn = 192.

• int m_snap

Snap value, starts out very small, equal to m_ppqn.

int m_measure_length

Provides the length of a measure in pulses or ticks.

int m_left_marker_tick

Holds the current location of the left (L) marker when arrow movement is in force.

int m_right_marker_tick

Holds the current location of the right (R) marker when arrow movement is in force.

• int m perf scale x

A class version of the global c_perf_scale_x factor.

· int m_timearea_y

A class version of the global c_timerarea_y factor.

Friends

class perfedit

Additional Inherited Members

12.54.1 Constructor & Destructor Documentation

12.54.1.1 perftime()

In the constructor you can only allocate colors; get_window() returns 0 because we have not been realized.

Note

Note that we still have to use a global constant in the base-class constructor; we cannot assign it to the corresponding member beforehand.

Parameters

p	Provides a reference to the main performance object of the application.	
parent	Provides a reference to the object that contains this object, so that this object can tell the parent to	
	queue up a drawing operation.	
hadjust	Provides the horizontal scrollbar object needed so that perftime can respond to scrollbar	
	cursor/thumb movement.	
ppqn	An optional override of the default PPQN value for the application.	

12.54.1.2 \sim perftime()

```
virtual seq64::perftime::\simperftime ( ) [inline], [virtual]
```

12.54.2 Member Function Documentation

```
12.54.2.1 reset()
```

```
void seq64::perftime::reset ( )
```

12.54.2.2 set_scale()

12.54.2.3 set_guides()

This function then fills in the background, and queues up a draw operation.

Parameters

snap	Provides the number of snap-pulses (pulses per snap interval) as calculated in perfedit::set_guides (). This is actually equal to the measure-pulses divided by the snap value in perfedit; the snap value defaults to 8.
measure	Provides the number of measure-pulses (pulses per measure) as calculated in perfedit::set_guides().

12.54.2.4 increment_size()

```
void seq64::perftime::increment_size ( ) [inline]
```

Compare it to perfroll::increment_size().

```
12.54.2.5 enqueue_draw()
```

void seq64::perftime::enqueue_draw () [private]

The parent perfedit will call perftime::queue_draw() on behalf of this object, and it will pass a perftime::enqueue_cdraw() to the peer perfedit's perftime, if the peer exists.

Redraws the background if the new zoom checked out.

Parameters

z Provides the zoom value, which is checked, and then copied into m_perf_scale_x.

```
12.54.2.7 draw_background()
```

```
void seq64::perftime::draw_background ( ) [private]
```

Note that m_measure_length == 0 will cause integer overflow.

```
12.54.2.8 draw_progress_on_window()
```

```
void seq64::perftime::draw_progress_on_window ( ) [private]
```

12.54.2.9 change_horz()

```
void seq64::perftime::change_horz ( ) [private]
```

Again, uses the constant, 16 [now offloaded to the new tick_offset() function.].

```
12.54.2.10 set_ppqn()
```

It also modifies m_snap, m_measure_length (but always for four measures!), and m_tick_offset.

Todo We need make the 4 constant variable per the number of beats (quarter-notes) per bar, and also at least make 16 (4x4) a meaningful manifest constant.

Parameters

ppqn The override value for the PPQN.

12.54.2.11 tick_to_pixel()

Parameters

tick

The horizontal tick value to convert to an x pixel value, based on tick-offset and the x-scale.

Returns

Returns the x-pixel representing the time location parameter.

12.54.2.12 pixel_to_tick()

Parameters

```
pixel The pixel value.
```

Returns

Returns the time value represented b the pixel.

12.54.2.13 tick_offset()

```
int seq64::perftime::tick_offset ( ) [inline], [private]
```

Returns

Returns m_4bar_offset * 16 * m_ppqn.

12.54.2.14 update_sizes()

```
void seq64::perftime::update_sizes ( ) [inline], [private]
```

12.54.2.15 idle_progress()

```
int seq64::perftime::idle_progress ( ) [inline], [private]
```

12.54.2.16 update_pixmap()

```
void seq64::perftime::update_pixmap ( ) [inline], [private]

12.54.2.17  draw_pixmap_on_window()

void seq64::perftime::draw_pixmap_on_window ( ) [inline], [private]

12.54.2.18  on_realize()
```

void seq64::perftime::on_realize () [private]

It is important to call the base-class version of this function.

The former work of this function is now done in base-class's on realize() and in its constructor now.

```
m_window = get_window();
m_gc = Gdk::GC::create(m_window);
m_window->clear();
set_size_request(10, m_timearea_y);
```

12.54.2.19 on_expose_event()

Redraws the background.

Note

The perfedit object is created early on. When brought on-screen from mainwand (the main window), first, perftime::on_realize() is called, then this event is called.

Parameters

```
ev The expose event, not used.
```

Returns

Always returns true.

12.54.2.20 on_button_press_event()

Added functionality to try to set the start-tick if ctrl-left-click is pressed.

Parameters

```
p0 The button event.
```

Returns

Always returns true.

Why is setting the start-tick disabled? We re-enable it and see if it works. To our surprise, it works, but it sticks between stop/pause and the next playback in the performance editor. We added a feature where stop sets the start-tick to the left tick (or the beginning tick).

12.54.2.21 on_size_allocate()

12.54.2.22 on_button_release_event()

"ev", The button event parameter, is not used.

Returns

Always returns false

12.54.2.23 key_press_event()

```
bool seq64::perftime::key_press_event (
    GdkEventKey * ev ) [private]
```

Can't get the keystroke events to be seen by perfroll or perftime here using the normal callback function for keystrokes, and not sure why. The perfedit object can call this function, and that call works, so the perfedit class, which does get keystrokes, calls this function to do the work.

This function uses the "I" key to activate the movement of the "L" marker with the arrow keys, by the interval of on snap value for each press. It also uses the "r" key to activate the movement of the "R" marker, and the "x" to deactivate either movement move.

Be aware that there is no visual feedback, as yet, that one is in the movement mode.

Also be aware the changing the name of this function from "key_press_event()" to "on_key_press_event()" will disrupt the process, causing keystrokes to not get here. Too tricky.

12.54.3 Friends And Related Function Documentation

12.54.3.1 perfedit

```
friend class perfedit [friend]
```

12.54.4 Field Documentation

12.54.4.1 m_parent

```
perfedit& seq64::perftime::m_parent [private]
```

We want to support two perfedit windows, but the children of perfedit will have to communicate changes requiring a redraw through the parent.

12.54.4.2 m_4bar_offset

```
int seq64::perftime::m_4bar_offset [private]
```

Also, why always 4/16 in the calculations of this value? Might be able to get rid of this member, though it's a bit tricky.

12.54.4.3 m_tick_offset

```
int seq64::perftime::m_tick_offset [private]
```

Why 16?

12.54.4.4 m_ppqn

```
int seq64::perftime::m_ppqn [private]
```

12.54.4.5 m_snap

```
int seq64::perftime::m_snap [private]
```

12.54.4.6 m_measure_length

```
int seq64::perftime::m_measure_length [private]
```

This value is $m_ppqn * 4$, though eventually we want to employ a more flexible representation of measure length. Supports perftime's keystroke processing.

```
12.54.4.7 m_left_marker_tick

int seq64::perftime::m_left_marker_tick [private]

Otherwise it is -1. Supports perftime's keystroke processing.

12.54.4.8 m_right_marker_tick

int seq64::perftime::m_right_marker_tick [private]

Otherwise it is -1. Supports perftime's keystroke processing.

12.54.4.9 m_perf_scale_x

int seq64::perftime::m_perf_scale_x [private]

12.54.4.10 m_timearea_y

int seq64::perftime::m_timearea_y [private]
```

12.55 seq64::rc_settings Class Reference

This class contains the options formerly named "global xxxxxx".

Public Member Functions

• rc_settings ()

Default constructor.

• rc_settings (const rc_settings &rhs)

Copy constructor.

rc_settings & operator= (const rc_settings &rhs)

Principal assignment operator.

• std::string config_filespec () const

Constructs the full path and file specification for the "rc" file based on whether or not the legacy Seq24 filenames are being used.

• std::string user_filespec () const

Constructs the full path and file specification for the "user" file based on whether or not the legacy Seq24 filenames are being used.

• void set_defaults ()

Sets the default values.

• bool auto_option_save () const

'Getter' function for member m_auto_option_save

· bool legacy_format () const

'Getter' function for member m_legacy_format

bool lash_support () const

'Getter' function for member m_lash_support

bool allow_mod4_mode () const

'Getter' function for member m_allow_mod4_mode

bool allow_snap_split () const

'Getter' function for member m_allow_snap_split

bool show_midi () const

'Getter' function for member m_show_midi

• bool priority () const

'Getter' function for member m_priority

• bool stats () const

'Getter' function for member m_stats

• bool pass_sysex () const

'Getter' function for member m_pass_sysex

bool with_jack_transport () const

'Getter' function for member m with jack transport

· bool with jack master () const

'Getter' function for member m_with_jack_master

bool with_jack_master_cond () const

'Getter' function for member m with jack master cond

bool with_jack () const

'Getter' function for member m_with_jack_transport m_with_jack_master, and m_with_jack_master_cond, to save client code some trouble.

bool filter_by_channel () const

'Getter' function for member m_song_start_mode,

bool manual_alsa_ports () const

'Getter' function for member m_manual_alsa_ports

bool reveal_alsa_ports () const

'Getter' function for member m_reveal_alsa_ports

• bool print_keys () const

'Getter' function for member m_print_keys

• bool device_ignore () const

'Getter' function for member m device ignore

• int device_ignore_num () const

'Getter' function for member m_device_ignore_num

interaction_method_t interaction_method () const

'Getter' function for member m_interaction_method

• const std::string & filename () const

'Getter' function for member m_filename

const std::string & jack_session_uuid () const

'Getter' function for member m_jack_session_uuid

const std::string & last_used_dir () const

'Getter' function for member m_last_used_dir

· const std::string & config_directory () const

'Getter' function for member m_config_directory

const std::string & config_filename () const

'Getter' function for member m config filename

· const std::string & user_filename () const

'Getter' function for member m_user_filename

const std::string & config_filename_alt () const

'Getter' function for member m_config_filename_alt;

const std::string & user_filename_alt () const

'Getter' function for member m_user_filename_alt

Protected Member Functions

void auto_option_save (bool flag)

'Setter' function for member m_auto_option_save

void legacy_format (bool flag)

'Setter' function for member m_legacy_format

void lash_support (bool flag)

'Setter' function for member m_lash_support

void allow_mod4_mode (bool flag)

'Setter' function for member m_allow_mod4_mode

void allow_snap_split (bool flag)

'Setter' function for member m_allow_snap_split

void show_midi (bool flag)

'Setter' function for member m_show_midi

void priority (bool flag)

'Setter' function for member m_priority

void stats (bool flag)

'Setter' function for member m_stats

void pass_sysex (bool flag)

'Setter' function for member m_pass_sysex

void with_jack_transport (bool flag)

'Setter' function for member m_with_jack_transport

void with_jack_master (bool flag)

'Setter' function for member m_with_jack_master

· void with_jack_master_cond (bool flag)

'Setter' function for member m_with_jack_master_cond

void filter_by_channel (bool flag)

'Setter' function for member m_song_start_mode,

void manual_alsa_ports (bool flag)

 $'Setter'\ function\ for\ member\ m_manual_alsa_ports$

void reveal_alsa_ports (bool flag)

'Setter' function for member m_reveal_alsa_ports

void print_keys (bool flag)

'Setter' function for member m_print_keys

• void device_ignore (bool flag)

'Setter' function for member m_device_ignore

void device_ignore_num (int value)

'Setter' function for member m_device_ignore_num However, please note that this value, while set in the options processing of the main module, does not appear to be used anywhere in the code in seq24, Sequencer24, and this application.

void interaction_method (interaction_method_t value)

'Setter' function for member m interaction method

• void filename (const std::string &value)

'Setter' function for member m_filename

void jack session uuid (const std::string &value)

'Setter' function for member m_jack_session_uuid

void last_used_dir (const std::string &value)

'Setter' function for member m last used dir

void config_directory (const std::string &value)

'Setter' function for member m config directory

• void set_config_files (const std::string &value)

'Setter' function for member m_config_filename and m_user_filename

void config_filename (const std::string &value)

'Setter' function for member m_config_filename ("rc")

void user_filename (const std::string &value)

'Setter' function for member m_user_filename ("usr")

void config_filename_alt (const std::string &value)

'Setter' function for member m_config_filename_alt

void user_filename_alt (const std::string &value)

'Setter' function for member m_user_filename_alt

Private Member Functions

std::string home_config_directory () const

Provides the directory for the configuration file, and also creates the directory if necessary.

Private Attributes

• bool m_auto_option_save

[auto-option-save] setting.

bool m_legacy_format

Write files in legacy format.

• bool m_lash_support

Enable LASH, if compiled in.

• bool m_allow_mod4_mode

Allow Mod4 to hold drawing mode.

bool m_allow_snap_split

Allow snap-split of a trigger.

bool m_show_midi

Show MIDI events to console.

bool m_priority

Run at high priority (Linux only).

• bool m_stats

Show some output statistics.

bool m_pass_sysex

Pass SysEx to outputs, not ready.

bool m_with_jack_transport

Enable synchrony with JACK.

bool m_with_jack_master

Serve as a JACK transport Master.

bool m_with_jack_master_cond

Serve as JACK Master if possible.

• bool m_filter_by_channel

Record only sequence channel data.

bool m_manual_alsa_ports

[manual-alsa-ports] setting.

bool m_reveal_alsa_ports

[reveal-alsa-ports] setting.

bool m print keys

Show hot-key in main window slot.

• bool m_device_ignore

From seq24 module, unused!

• int m_device_ignore_num

From seq24 module, unused!

interaction_method_t m_interaction_method

[interaction-method]

• std::string m_filename

Provides the name of current MIDI file.

std::string m_jack_session_uuid

Holds the JACK UUID value that makes this JACK connection unique.

std::string m_last_used_dir

Holds the directory from which the last MIDI file was opened (or saved).

std::string m_config_directory

Holds the current "rc" and "user" configuration directory.

std::string m_config_filename

Holds the current "rc" configuration filename.

std::string m_user_filename

Holds the current "user" configuration filename.

std::string m_config_filename_alt

Holds the legacy "rc" filename, ".seq24rc".

· std::string m user filename alt

Holds the legacy "user" filename, ".seq24usr".

Friends

- · class optionsfile
- class options
- · class mainwnd
- int parse_command_line_options (perform &p, int argc, char *argv [])

Parses the command-line options on behalf of the application.

• bool help_check (int argc, char *argv [])

Checks to see if the first option is a help or version argument, just so we can skip the "Reading configuration ..." messages.

12.55.1 Detailed Description

It gives us a whole lot more encapsulation and control over how the options of the "rc" file (optionsfile) are set and used. Note that this class does not support the hot-keys options; those are handled in the keys_perform class.

12.55.2 Constructor & Destructor Documentation

rhs The source of the data for the copy.

12.55.3 Member Function Documentation

12.55.3.1 operator=()

Parameters

rhs The source of the data for the assignment.

Returns

Returns a reference to the destination for use in serial assignments.

12.55.3.2 config_filespec()

```
std::string seq64::rc_settings::config_filespec ( ) const
```

Returns

If home_config_directory() returns a non-empty string, then the legacy or normal "rc" configuration file-name is appended to that result, and returned. Otherwise, an empty string is returned.

12.55.3.3 user_filespec()

```
std::string seq64::rc_settings::user_filespec ( ) const
```

Returns

If home_config_directory() returns a non-empty string, then the legacy or normal "user" configuration file-name is appended to that result, and returned. Otherwise, an empty string is returned.

12.55.3.4 set_defaults()

```
void seq64::rc_settings::set_defaults ( )

12.55.3.5 auto_option_save() [1/2]

bool seq64::rc_settings::auto_option_save ( ) const [inline]
```

```
12.55.3.6 legacy_format() [1/2]
bool seq64::rc_settings::legacy_format ( ) const [inline]
12.55.3.7 lash_support() [1/2]
bool seq64::rc_settings::lash_support ( ) const [inline]
12.55.3.8 allow_mod4_mode() [1/2]
bool seq64::rc_settings::allow_mod4_mode ( ) const [inline]
12.55.3.9 allow_snap_split() [1/2]
bool seq64::rc_settings::allow_snap_split ( ) const [inline]
12.55.3.10 show_midi() [1/2]
bool seq64::rc_settings::show_midi ( ) const [inline]
12.55.3.11 priority() [1/2]
bool seq64::rc_settings::priority ( ) const [inline]
12.55.3.12 stats() [1/2]
bool seq64::rc_settings::stats ( ) const [inline]
12.55.3.13 pass_sysex() [1/2]
bool seq64::rc_settings::pass_sysex ( ) const [inline]
12.55.3.14 with_jack_transport() [1/2]
bool seq64::rc_settings::with_jack_transport ( ) const [inline]
12.55.3.15 with_jack_master() [1/2]
bool seq64::rc_settings::with_jack_master ( ) const [inline]
```

```
12.55.3.16 with_jack_master_cond() [1/2]
bool seq64::rc_settings::with_jack_master_cond ( ) const [inline]
12.55.3.17 with_jack()
bool seq64::rc_settings::with_jack ( ) const [inline]
12.55.3.18 filter_by_channel() [1/2]
bool seq64::rc_settings::filter_by_channel ( ) const [inline]
bool song_start_mode () const { return m_song_start_mode; } 'Getter' function for member m_filter_by_channel
12.55.3.19 manual_alsa_ports() [1/2]
bool seq64::rc_settings::manual_alsa_ports ( ) const [inline]
12.55.3.20 reveal_alsa_ports() [1/2]
bool seq64::rc_settings::reveal_alsa_ports ( ) const [inline]
12.55.3.21 print_keys() [1/2]
bool seq64::rc_settings::print_keys ( ) const [inline]
12.55.3.22 device_ignore() [1/2]
bool seq64::rc_settings::device_ignore ( ) const [inline]
12.55.3.23 device_ignore_num() [1/2]
int seq64::rc_settings::device_ignore_num ( ) const [inline]
12.55.3.24 interaction_method() [1/2]
interaction_method_t seq64::rc_settings::interaction_method ( ) const [inline]
12.55.3.25 filename() [1/2]
const std::string& seq64::rc_settings::filename ( ) const [inline]
```

```
12.55.3.26 jack_session_uuid() [1/2]
const std::string& seq64::rc_settings::jack_session_uuid ( ) const [inline]
12.55.3.27 last_used_dir() [1/2]
const std::string& seq64::rc_settings::last_used_dir ( ) const [inline]
12.55.3.28 config_directory() [1/2]
const std::string& seq64::rc_settings::config_directory ( ) const [inline]
12.55.3.29 config_filename() [1/2]
const std::string& seq64::rc_settings::config_filename ( ) const [inline]
12.55.3.30 user_filename() [1/2]
const std::string& seq64::rc_settings::user_filename ( ) const [inline]
12.55.3.31 config_filename_alt() [1/2]
const std::string& seq64::rc_settings::config_filename_alt ( ) const [inline]
12.55.3.32 user_filename_alt() [1/2]
const std::string& seq64::rc_settings::user_filename_alt ( ) const [inline]
12.55.3.33 auto_option_save() [2/2]
void seq64::rc\_settings::auto\_option\_save (
             bool flag ) [inline], [protected]
12.55.3.34 legacy_format() [2/2]
void seq64::rc_settings::legacy_format (
             bool flag ) [inline], [protected]
12.55.3.35 lash_support() [2/2]
void seq64::rc_settings::lash_support (
             bool flag ) [inline], [protected]
```

```
12.55.3.36 allow_mod4_mode() [2/2]
void seq64::rc_settings::allow_mod4_mode (
             bool flag ) [inline], [protected]
12.55.3.37 allow_snap_split() [2/2]
void seq64::rc_settings::allow_snap_split (
             bool flag ) [inline], [protected]
12.55.3.38 show_midi() [2/2]
void seq64::rc_settings::show_midi (
            bool flag ) [inline], [protected]
12.55.3.39 priority() [2/2]
void seq64::rc_settings::priority (
             bool flag ) [inline], [protected]
12.55.3.40 stats() [2/2]
void seq64::rc_settings::stats (
             bool flag ) [inline], [protected]
12.55.3.41 pass_sysex() [2/2]
void seq64::rc_settings::pass_sysex (
             bool flag ) [inline], [protected]
12.55.3.42 with_jack_transport() [2/2]
void seq64::rc_settings::with_jack_transport (
             bool flag ) [inline], [protected]
12.55.3.43 with_jack_master() [2/2]
void seq64::rc_settings::with_jack_master (
             bool flag ) [inline], [protected]
12.55.3.44 with_jack_master_cond() [2/2]
\verb"void seq64::rc_settings::with_jack_master_cond" (
             bool flag ) [inline], [protected]
```

value

The value to use to make the setting.

```
12.55.3.45 filter_by_channel() [2/2]
void seq64::rc\_settings::filter\_by\_channel (
             bool flag ) [inline], [protected]
void song_start_mode (bool flag) { m_song_start_mode = flag; } 'Setter' function for member m_filter_by_channel
12.55.3.46 manual_alsa_ports() [2/2]
void seq64::rc_settings::manual_alsa_ports (
             bool flag ) [inline], [protected]
12.55.3.47 reveal_alsa_ports() [2/2]
void seq64::rc_settings::reveal_alsa_ports (
              bool flag ) [inline], [protected]
12.55.3.48 print_keys() [2/2]
void seq64::rc_settings::print_keys (
              bool flag ) [inline], [protected]
12.55.3.49 device_ignore() [2/2]
void seq64::rc_settings::device_ignore (
             bool flag ) [inline], [protected]
12.55.3.50 device_ignore_num() [2/2]
void seq64::rc_settings::device_ignore_num (
             int value ) [protected]
Parameters
 value
         The value to use to make the setting.
12.55.3.51 interaction_method() [2/2]
void seq64::rc_settings::interaction_method (
              interaction_method_t value ) [protected]
Parameters
```

value The value to use to make the setting.

12.55.3.53 jack_session_uuid() [2/2]

Parameters

value The value to use to make the setting.

12.55.3.54 last_used_dir() [2/2]

Parameters

value The value to use to make the setting.

12.55.3.55 config_directory() [2/2]

Parameters

value The value to use to make the setting.

12.55.3.56 set_config_files()

Implements the -config option to change both configuration files ("rc" and "usr") with one option.

value

The value to use to make the setting, if the string is not empty. If the value has an extension, it is stripped first.

```
12.55.3.57 config_filename() [2/2]
```

Parameters

value

The value to use to make the setting, if the string is not empty. If there is no period in the string, then ".rc" is appended to the end of the filename.

12.55.3.58 user_filename() [2/2]

Parameters

value

The value to use to make the setting, if the string is not empty. If there is no period in the string, then ".usr" is appended to the end of the filename.

12.55.3.59 config_filename_alt() [2/2]

Parameters

value The value to use to make the setting, if the string is not empty.

12.55.3.60 user_filename_alt() [2/2]

Parameters

value The value to use to make the setting.

12.55.3.61 home_config_directory()

```
std::string seq64::rc_settings::home_config_directory ( ) const [private]
```

If the legacy format is in force, then the home directory for the configuration is (in Linux) "/home/username", and the configuration file is ".seq24rc".

If the new format is in force, then the home directory is (in Linux) "/home/username/.config/sequencer64", and the configuration file is "sequencer64.rc".

Returns

Returns the selected home configuration directory. If it does not exist, or could not be created, then an empty string is returned.

12.55.4 Friends And Related Function Documentation

12.55.4.1 optionsfile

```
friend class optionsfile [friend]
```

12.55.4.2 options

```
friend class options [friend]
```

12.55.4.3 mainwnd

```
friend class mainwnd [friend]
```

12.55.4.4 parse_command_line_options

Note that, since we call this function twice (once before the configuration files are parsed, and once after), we have to make sure that the global value optind is reset to 0 before calling this function. Note that the traditional reset value for optind is 1, but 0 is used in GNU code to trigger the internal initialization routine of get_opt().

Parameters

argc	The number of command-line arguments.
argv	The array of command-line argument pointers.

Returns

Returns the value of optind if no help-related options were provided.

12.55.4.5 help_check

Also check for the –legacy option. Finally, it also checks for the "?" option that people sometimes use as a guess to get help.

Parameters

argo	The number of command-line arguments.
arg	The array of command-line argument pointers.

Returns

Returns true only if -v, -V, -version, -h, -help, or "?" were encountered. If the legacy options occurred, then rc().legacy_format(true) is called, as a side effect, because it will be needed before we parse the options.

12.55.5 Field Documentation

```
12.55.5.1 m_auto_option_save
```

```
bool seq64::rc_settings::m_auto_option_save [private]
```

12.55.5.2 m_legacy_format

```
bool seq64::rc_settings::m_legacy_format [private]
```

12.55.5.3 m_lash_support

```
bool seq64::rc_settings::m_lash_support [private]
```

12.55.5.4 m_allow_mod4_mode

```
bool seq64::rc_settings::m_allow_mod4_mode [private]
```

12.55.5.5 m_allow_snap_split

bool seq64::rc_settings::m_allow_snap_split [private]

```
12.55.5.6 m_show_midi
bool seq64::rc_settings::m_show_midi [private]
12.55.5.7 m_priority
bool seq64::rc_settings::m_priority [private]
12.55.5.8 m_stats
bool seq64::rc_settings::m_stats [private]
12.55.5.9 m_pass_sysex
bool seq64::rc_settings::m_pass_sysex [private]
12.55.5.10 m_with_jack_transport
bool seq64::rc_settings::m_with_jack_transport [private]
12.55.5.11 m_with_jack_master
bool seq64::rc_settings::m_with_jack_master [private]
12.55.5.12 m_with_jack_master_cond
bool seq64::rc_settings::m_with_jack_master_cond [private]
12.55.5.13 m_filter_by_channel
bool seq64::rc_settings::m_filter_by_channel [private]
12.55.5.14 m_manual_alsa_ports
bool seq64::rc_settings::m_manual_alsa_ports [private]
12.55.5.15 m_reveal_alsa_ports
bool seq64::rc_settings::m_reveal_alsa_ports [private]
```

```
12.55.5.16 m_print_keys
bool seq64::rc_settings::m_print_keys [private]
12.55.5.17 m_device_ignore
bool seq64::rc_settings::m_device_ignore [private]
12.55.5.18 m_device_ignore_num
int seq64::rc_settings::m_device_ignore_num [private]
12.55.5.19 m_interaction_method
interaction_method_t seq64::rc_settings::m_interaction_method [private]
12.55.5.20 m_filename
std::string seq64::rc_settings::m_filename [private]
12.55.5.21 m_jack_session_uuid
std::string seq64::rc_settings::m_jack_session_uuid [private]
12.55.5.22 m_last_used_dir
std::string seq64::rc_settings::m_last_used_dir [private]
12.55.5.23 m_config_directory
std::string seq64::rc_settings::m_config_directory [private]
This value is "\sim/.config/sequencer64" by default.
12.55.5.24 m_config_filename
std::string seq64::rc_settings::m_config_filename [private]
```

This value is "sequencer64.rc" by default.

```
12.55.5.25 m_user_filename
std::string seq64::rc_settings::m_user_filename [private]
This value is "sequencer64.usr" by default.

12.55.5.26 m_config_filename_alt
std::string seq64::rc_settings::m_config_filename_alt [private]

12.55.5.27 m_user_filename_alt
std::string seq64::rc_settings::m_user_filename_alt [private]
```

12.56 seq64::rect Class Reference

A small helper class representing a rectangle.

Data Fields

• int x

The x-coordinate of the origin of the rectangle.

• int y

The y-coordinate of the origin of the rectangle.

• int height

The height of the rectangle, in units of pixels.

int width

The width of the rectangle, in units of pixels.

12.56.1 Field Documentation

```
12.56.1.1 x
int seq64::rect::x

12.56.1.2 y
int seq64::rect::y

12.56.1.3 height
int seq64::rect::height
```

12.56.1.4 width

int seq64::rect::width

12.57 seq64::gui_drawingarea_gtk2::rect Struct Reference

A small helper structure representing a rectangle.

Data Fields

- int x
- int y
- · int height
- int width

12.57.1 Field Documentation

12.57.1.1 x

int seq64::gui_drawingarea_gtk2::rect::x

12.57.1.2 y

int seq64::gui_drawingarea_gtk2::rect::y

12.57.1.3 height

int seq64::gui_drawingarea_gtk2::rect::height


12.57.1.4 width

int seq64::gui_drawingarea_gtk2::rect::width

12.58 seq64::Seq24PerfInput Class Reference

Implements the default (Seq24) performance input characteristics of this application.

Inheritance diagram for seq64::Seq24PerfInput:



Public Member Functions

- Seq24PerfInput ()
- bool on_button_press_event (GdkEventButton *a_ev, perfroll &roll)

 Handles the normal variety of button-press event.
- bool on_button_release_event (GdkEventButton *a_ev, perfroll &roll)
 - Handles various button-release events.
- bool on_motion_notify_event (GdkEventMotion *a_ev, perfroll &roll)

Handles the normal motion-notify event.

Private Member Functions

virtual void activate_adding (bool a_adding, perfroll &roll)

A popup menu (which one?) calls this.

bool handle_motion_key (bool is_left, perfroll &roll)

Handles the keystroke motion-notify event for moving a pattern back and forth in the performance.

Private Attributes

· midipulse m effective tick

The current tick for the current segment?

Friends

· class perfroll

Additional Inherited Members

12.58.1 Constructor & Destructor Documentation

12.58.1.1 Seq24PerfInput()

```
seq64::Seq24PerfInput::Seq24PerfInput ( ) [inline]
```

12.58.2 Member Function Documentation

12.58.2.1 on_button_press_event()

Is there any easy way to use ctrl-left-click as the middle button here?

Stazed:

```
roll.m_drop_y will be adjusted by perfroll::change_vert() for any scroll after it was originally selected. The call here to draw_drawable_row() [now folded into draw_all()] will have the wrong y location and un-select will not occur (or the wrong sequence will be unselected) if the user scrolls the track up or down to a new y location, if not adjusted.
```

Returns

Returns true if a modification occurred.

Implements seq64::AbstractPerfInput.

12.58.2.2 on_button_release_event()

Any use for the middle-button or ctrl-left-click we can add?

Returns

Returns true if any modification occurred.

Implements seq64::AbstractPerfInput.

12.58.2.3 on_motion_notify_event()

Returns

Returns true if a modification occurs. This function used to always return true.

Implements seq64::AbstractPerfInput.

12.58.2.4 activate_adding()

What does it mean?

Implements seq64::AbstractPerfInput.

12.58.2.5 handle_motion_key()

What happens when the mouse is used to drag the pattern is that, first, roll.m_drop_tick is set by left-clicking into the pattern to select it. As the pattern is dragged, the drop-tick value does not change, but the tick (converted from the moving x value) does.

Then the button-handler sets roll.m_moving = true, and calculates roll.m_drop_tick_trigger_offset = roll.m_drop_tick - p.get_sequence(dropseq)->selected_trigger_start();

The motion handler sees that roll.m_moving is true, gets the new tick value from the new x value, offsets it, and calls p.get_sequence(dropseq)->move_selected_triggers_to(tick, true).

When the user releases the left button, then roll.m_growing is turned of and the roll draw_all()'s.

is_left	False denotes the right arrow key, and true denotes the left arrow key.	
roll	Provides a reference to the parent roll, which keeps track of most of the information about the status of	
	the window.	

Returns

Returns true if there was some action able to happen that would necessitate a window update. We've updated triggers::move_selected() [called indirectly near the end of this routine] to return false if no more movement could be made. This prevents this routine from moving way ahead after movement of the selected (in the user-interface) trigger stops.

Implements seq64::AbstractPerfInput.

12.58.3 Friends And Related Function Documentation

12.58.3.1 perfroll

```
friend class perfroll [friend]
```

12.58.4 Field Documentation

12.58.4.1 m_effective_tick

```
midipulse seq64::Seq24PerfInput::m_effective_tick [private]
```

12.59 seq64::Seq24SeqEventInput Struct Reference

This structure implement the normal interaction methods for Seq24.

Public Member Functions

• Seq24SeqEventInput ()

Default constructor.

void set_adding (bool adding, seqevent &ths)

Changes the mouse cursor to a pencil or a left pointer in the given seqevent object, depending on the first parameter.

• bool on_button_press_event (GdkEventButton *ev, seqevent &ths)

Implements the on-button-press event callback.

• bool on_button_release_event (GdkEventButton *ev, seqevent &ths)

Implements the on-button-release callback.

bool on_motion_notify_event (GdkEventMotion *ev, seqevent &ths)

Implements the on-motion-notify event.

Data Fields

• bool m_adding

True if we're adding events via the mouse.

12.59.1 Constructor & Destructor Documentation

12.59.1.1 Seq24SeqEventInput()

```
seq64::Seq24SeqEventInput::Seq24SeqEventInput ( ) [inline]
```

12.59.2 Member Function Documentation

12.59.2.1 set_adding()

```
void seq64::Seq24SeqEventInput::set_adding (
          bool adding,
          seqevent & seqev )
```

Modifies m_adding as well.

Parameters

adding	The value to set m_adding to, and if true, sets the mouse cursor to a pencil icon, otherwise sets it to a standard mouse-pointer icon.
seqev	The seqevent whose window will be set to "adding" mode.

12.59.2.2 on_button_press_event()

Set values for dragging, then reset the box that holds dirty redraw spot. Then do the rest.

Parameters

ev	The button event for the press of a mouse button.
seqev	Provides the sequeent strip to be affected by this button event.

Returns

Returns true if a likely modification was made. This function used to return true all the time.

Needs update. seqev.m_seq.unselect(); ???????

12.59.2.3 on_button_release_event()

Parameters

ev	The button event for the release of a mouse button.	
seqev	Provides the sequeent strip to be affected by this button event.	

Returns

Returns true if a likely modification was made. This function used to return true all the time.

12.59.2.4 on_motion_notify_event()

Parameters

ev	The button event for the motion of the mouse cursor.
seqev	Provides the sequeent strip to be affected by this button event.

Returns

Returns true if a likely modification was made. This function used to return true all the time.

12.59.3 Field Documentation

12.59.3.1 m_adding

```
bool seq64::Seq24SeqEventInput::m_adding
```

12.60 seq64::seqdata Class Reference

This class supports drawing piano-roll eventis on a window.

Inheritance diagram for seq64::seqdata:



Public Member Functions

- seqdata (sequence &seq, perform &p, int zoom, Gtk::Adjustment &hadjust)

 Principal constructor.
- virtual ∼seqdata ()

Let's provide a do-nothing virtual destructor.

• void reset ()

This function calls update_size().

void redraw ()

Calls change_horz() to update the pixmap and queue up a redraw operation.

void set zoom (int a zoom)

Sets the zoom to the given value and resets the view via the reset function.

void set_data_type (midibyte status, midibyte control)

Sets the status to the given value, and the control to the optional given value, which defaults to 0, then calls redraw().

Private Member Functions

• int idle_redraw ()

Draws events on this object's built-in window and pixmap.

void update_sizes ()

Updates the sizes in the pixmap if the view is realized, and queues up a draw operation.

void update_pixmap ()

Simply calls draw_events_on_pixmap().

void draw_line_on_window ()

Draws on vertical line on the data window.

void xy_to_rect (int x1, int y1, int x2, int y2, int &rx, int &ry, int &rw, int &rh)

This function takes two points, and returns an XWin rectangle, returned via the last four parameters.

void draw_events_on (Glib::RefPtr< Gdk::Drawable > drawable)

Draws events on the given drawable object.

• void change horz ()

Change the scrolling offset on the x-axis, and redraw.

void convert_x (int x, midipulse &tick)

This function takes screen coordinates, and gives the horizontaol tick value based on the current zoom, returned via the second parameter.

• void render_number (Glib::RefPtr< Gdk::Pixmap > &pixmap, int x, int y, const char *const num)

Convenience function for rendering numbers.

void draw_events_on_pixmap ()

Simply calls draw_events_on() for this object's built-in pixmap.

void draw_pixmap_on_window ()

Simply queues up a draw operation.

void on_realize ()

Implements the on-realization event, by calling the base-class version and then allocating the resources that could not be allocated in the constructor.

bool on_expose_event (GdkEventExpose *ev)

Implements the on-expose event by calling draw_drawable() on the event.

bool on_button_press_event (GdkEventButton *ev)

Implements a mouse button-press event.

 $\bullet \ \ bool \ on_button_release_event \ (GdkEventButton *ev)\\$

Implement a button-release event.

bool on_motion_notify_event (GdkEventMotion *ev)

Handles a motion-notify event.

bool on_leave_notify_event (GdkEventCrossing *ev)

Handles an on-leave notification event.

• bool on_scroll_event (GdkEventScroll *ev)

Implements the on-scroll event.

• void on_size_allocate (Gtk::Allocation &)

Handles a size-allocation event by updating m_window_x and m_window_y, and then updating all of the sizes of the data pane in update_sizes().

Private Attributes

· sequence & m seq

Points to the sequence whose data is being affected by this class.

• int m zoom

Sets the zoom value for this part of the sequence editor, one pixel == m_zoom ticks, i.e.

int m_scroll_offset_ticks

The value of the leftmost tick in the data pane.

• int m scroll offset x

The value of the leftmost pixel in the data pane.

· int m number w

The adjusted width of a digit in a data number.

· int m number h

The adjusted height of all digits in a data number.

int m_number_offset_y

A new value to make it easier to adapt the vertical number drawing of a data item's numeric value to a different font.

• midibyte m_status

Holds the status byte of the next event in the sequence, and indicates What the data window is currently editing or drawing.

• midibyte m_cc

Holds the MIDI CC byte of the next event in the sequence, and indicates What the data window is currently editing or drawing.

Glib::RefPtr< Gdk::Pixmap > m_numbers [c_dataarea_y]

Holds the pixmaps for each number (0 to 127) that can be drawn for a data value in the data pane.

GdkRectangle m_old

This rectangle is used in blanking out a data line in draw line on window().

- bool m_drag_handle
- bool m dragging

This value is true if the mouse is being dragged in the data pane, which is done in order to change the height and value of each data line.

Friends

- · class Ifownd
- · class seqevent
- class segroll

Additional Inherited Members

12.60.1 Constructor & Destructor Documentation

12.60.1.1 segdata()

In the constructor one can only allocate colors, get_window() returns 0 because this pane has not yet been realized.

seq	The sequence that is being displayed and edited by this data pane.	
p	The performance object that oversees all of the sequences. This object is needed here only to access the perform::modify() function.	
zoom	The starting zoom of this pane.	
hadjust	The horizontal adjustment object provided by the parent class, seqedit, that created this pane.	

```
12.60.1.2 \sim seqdata()
```

```
virtual seq64::seqdata::\simseqdata ( ) [inline], [virtual]
```

12.60.2 Member Function Documentation

```
12.60.2.1 reset()
```

```
void seq64::seqdata::reset ( )
```

Then, regardless of whether the view is realized, updates the pixmap and queues up a draw operation.

Note

If it weren't for the is_realized() condition, we could just call update_sizes(), which does all this anyway.

12.60.2.2 redraw()

```
void seq64::seqdata::redraw ( ) [inline]
```

12.60.2.3 set_zoom()

```
void seq64::seqdata::set_zoom ( int \ z \ )
```

Called by seqedit::set_zoom(), which validates the zoom value.

Parameters

z The desired zoom value, assumed to be validated already. See the seqedit::set_zoom() function.

12.60.2.4 set_data_type()

Perhaps we should check that at least one of the parameters causes a change.

Parameters

status	The MIDI event byte (status byte) to set.
control	The MIDI CC value to set.

12.60.2.5 idle_redraw()

```
int seq64::seqdata::idle_redraw ( ) [private]
```

This drawing is done only if there is no dragging in progress, to guarantee no flicker.

12.60.2.6 update_sizes()

```
void seq64::seqdata::update_sizes ( ) [private]
```

It creates a pixmap with window dimensions given by m_window_x and m_window_y.

We thought there was a potential memory leak, since m_pixmap is created every time the window is resized, but valgrind says otherwise... maybe. An awful lot of Gtk leaks!

12.60.2.7 update_pixmap()

```
void seq64::seqdata::update_pixmap ( ) [private]
```

12.60.2.8 draw_line_on_window()

```
void seq64::seqdata::draw_line_on_window ( ) [private]
```

12.60.2.9 xy_to_rect()

```
void seq64::seqdata::xy_to_rect (
    int x1,
    int y1,
    int x2,
    int y2,
    int & rx,
    int & ry,
    int & rw,
    int & rh ) [private]
```

It checks the mins/maxes, then fills in x, y, and width, height.

Parameters

	x1	The input x value for the first data point.
	y1	The input y value for the first data point.
Generated	ыўВох	ygEhe input x value for the second data point.
	y2	The input y value for the second data point.
out	rx	The output for the x value of the XWin rectangle.
out	ry	The output for the y value of the XWin rectangle.

12.60.2.10 draw_events_on()

Very similar to seqevent :: draw_events_on(). And yet it doesn't handle zooming as well, must fix!

Stazed:

For Note On there can be multiple events on the same vertical in which the selected item can be covered. For Note On the selected item needs to be drawn last so it can be seen. So, for other events the variable num_selected_events will be -1 for ALL_EVENTS. For Note On only, the variable will be the number of selected events. If 0 then only one pass is needed. If > 0 then two passes are needed, one for unselected (first), and one for selected (last). For the first pass, if any events are selected, the selection type is EVENTS_UNSELECTED. For the second pass, it will be set to num_selected_events.

We now draw the data line for selected event in dark orange, instead of black. We're not likely to adopt the Stazed convention of drawing in blue. Also, there seem to be some bugs in how the data selection works. Needs more evaluation.

Also, if we decide to draw handle on each vertical data line, it would look nicer if a circle.

Parameters

```
drawable The given drawable object.
```

12.60.2.11 change_horz()

```
void seq64::seqdata::change_horz ( ) [private]
```

Basically identical to seqevent::change_horz().

12.60.2.12 convert_x()

12.60.2.13 render_number()

```
void seq64::seqdata::render_number (
         Glib::RefPtr< Gdk::Pixmap > & pixmap,
         int x,
         int y,
         const char *const num ) [inline], [private]
```

pixmap	The reference pointer to the GDK pixmap onto which this number will be drawing.
Х	The x-coordinate of the position of the text.
У	The y-coordinate of the position of the text.
num	The number to be rendered. This should be a string reference, but oh well.

12.60.2.14 draw_events_on_pixmap()

```
void seq64::seqdata::draw_events_on_pixmap ( ) [inline], [private]
```

12.60.2.15 draw_pixmap_on_window()

```
void seq64::seqdata::draw_pixmap_on_window ( ) [inline], [private]
```

12.60.2.16 on_realize()

```
void seq64::seqdata::on_realize ( ) [private]
```

It also connects up the change_horz() function.

Note that this function creates a small pixmap for every possible y-value, where y ranges from 0 to MIDI_COUNT \leftarrow _MAX-1 = 127. It then fills each pixmap with a numeric representation of that y value, up to three digits (left-padded with spaces).

12.60.2.17 on_expose_event()

Parameters

ev	Provides the expose-event.
----	----------------------------

Returns

Always returns true.

12.60.2.18 on_button_press_event()

This function pushes the undo information for the sequence, sets the drop-point, resets the box that holds dirty redraw spot, and sets m_dragging to true.

ev Provides the button-press event.

Returns

Always returns true.

12.60.2.19 on_button_release_event()

Sets the current point. If m_dragging is true, then the sequence data is changed, the performance modification flag is set, and m_dragging is reset.

Parameters

ev Provides the button-release event.

Returns

Returns true if a modification occurred, and in that case also sets the perform modification flag.

12.60.2.20 on_motion_notify_event()

It converts the x,y of the mouse to ticks, then sets the events in the event-data-range, updates the pixmap, draws events in the window, and draws a line on the window.

Parameters

ev The motion event.

Returns

Returns true if a change in event data occurred. If true, then the perform modification flag is set.

12.60.2.21 on_leave_notify_event()

Parameter "p0", the crossing point for the event, is unused.

```
12.60.2.22 on_scroll_event()
```

This scroll event only handles basic scrolling, without any modifier keys such as the Ctrl of Shift masks. If there is a note (seqroll pane) or event (seqevent pane) selected, and mouse hovers over the data area (seqdata pane), then this scrolling action will increase or decrease the value of the data item, which lengthens of shortens the line drawn.

Todo DOCUMENT the segdata scrolling behavior in the documentation projects.

Parameters

ev Provides the scroll-event.

Returns

Always returns true.

12.60.2.23 on_size_allocate()

Parameters

r Provides the allocation event.

12.60.3 Friends And Related Function Documentation

12.60.3.1 Ifownd

```
friend class lfownd [friend]
```

12.60.3.2 seqevent

```
friend class sequent [friend]
```

12.60.3.3 seqroll

```
friend class seqroll [friend]
```

12.60.4 Field Documentation

midibyte seq64::seqdata::m_status [private]


```
12.60.4.1 m_seq
sequence& seq64::seqdata::m_seq [private]
12.60.4.2 m_zoom
int seq64::seqdata::m_zoom [private]
the unit is ticks/pixel.
12.60.4.3 m_scroll_offset_ticks
int seq64::seqdata::m_scroll_offset_ticks [private]
Adjusted in the change horz() function.
12.60.4.4 m_scroll_offset_x
int seq64::seqdata::m_scroll_offset_x [private]
Adjusted in the change_horz() function. It is the offset ticks divided by the zoom value, i.e. the unit is pixels..
12.60.4.5 m_number_w
int seq64::seqdata::m_number_w [private]
By "adjusted", well this is just a minor tweak for appearances.
12.60.4.6 m_number_h
int seq64::seqdata::m_number_h [private]
Basically, the character height times 3. By "adjusted", well this is just a minor tweak for appearances.
12.60.4.7 m_number_offset_y
int seq64::seqdata::m_number_offset_y [private]
This value was hardwired as 8, for a character height of 10.
12.60.4.8 m_status
```

```
12.60.4.9 m_cc
midibyte seq64::seqdata::m_cc [private]
12.60.4.10 m_numbers
Glib::RefPtr<Gdk::Pixmap> seq64::seqdata::m_numbers[c_dataarea_y] [private]
This array is filled only once, in the on_realize() function.
12.60.4.11 m_old
GdkRectangle seq64::seqdata::m_old [private]
12.60.4.12 m_drag_handle
bool seq64::seqdata::m_drag_handle [private]
12.60.4.13 m_dragging
bool seq64::seqdata::m_dragging [private]
```

12.61 seq64::seqedit Class Reference

Implements the Pattern Editor, which has references to:

Inheritance diagram for seq64::seqedit:



Public Member Functions

- seqedit (perform &perf, sequence &seq, int pos, int ppqn=SEQ64_USE_DEFAULT_PPQN)
 Principal constructor.
- virtual ∼seqedit ()

A rote destructor.

Private Member Functions

void set_zoom (int zoom)

Selects the given zoom value.

void set snap (int snap)

Selects the given snap value, which is the number of ticks in a snap-sized interval.

void set_note_length (int note_length)

Selects the given note-length value.

void set beats per bar (int bpm)

Set the bpm (beats per measure) value, using the given parameter, and some internal values passed to apply_\leftarrow length().

void set beat width (int bw)

Set the bw (beat width) value, using the given parameter, and some internal values passed to apply_length().

void set transpose image (bool istransposable)

Changes the image used for the transpose button.

void set_rec_vol (int recvol)

Passes the given parameter to sequence::set_rec_vol().

void horizontal_adjust (double step)

This function provides optimization for the on_scroll_event() function.

void vertical_adjust (double step)

This function provides optimization for the on_scroll_event() function.

void horizontal_set (double value)

Sets the exact position of a horizontal scroll-bar.

• void vertical_set (double value)

Sets the exact position of a vertical scroll-bar.

void set_measures (int lim)

Set the measures value, using the given parameter, and some internal values passed to apply_length().

· void apply_length (int bpm, int bw, int measures)

Sets the sequence length based on the three given parameters.

long get_measures ()

Calculates the measures value based on the bpm (beats per measure), ppqn (parts per quarter note), and bw (beat width) values, and returns the resultant measures value.

• void set_midi_channel (int midichannel, bool user_change=false)

Selects the given MIDI channel parameter in the main sequence object, so that it will use that channel.

void set midi bus (int midibus, bool user change=false)

Selects the given MIDI buss parameter in the main sequence object, so that it will use that buss.

• void set scale (int scale)

Selects the given scale value.

- void set_chord (int chord)
- void set_key (int note)

Selects the given key (signature) value.

void set background sequence (int seq)

Draws the given background sequence on the Pattern editor so that the musician has something to see that can be played against.

void transpose_change_callback ()

Passes the transpose status to the sequence object.

• void name_change_callback ()

Set the name for the main sequence to this object's entry name.

void play_change_callback ()

Passes the play status to the sequence object.

void record_change_callback ()

Passes the recording status to the sequence object.

void q_rec_change_callback ()

Passes the quantized-recording status to the sequence object.

• void thru change callback ()

Passes the MIDI Thru status to the sequence object.

void undo_callback ()

Pops an undo operation from the sequence object, and then tells the segroll, seqtime, seqdata, and seqevent objects to redraw.

void redo callback ()

Pops a redo operation from the sequence object, and then tell the segroll, seqtime, seqdata, and seqevent objects to redraw.

void set data type (midibyte status, midibyte control=0)

Sets the data type based on the given parameters.

- void update all windows ()
- · void fill top bar ()

This function inserts the user-interface items into the top bar or panel of the pattern editor; this bar has two rows of user interface elements.

void create_menus ()

Creates the various menus by pushing menu elements into the menus.

• void popup_menu (Gtk::Menu *menu)

Pops up the given pop-up menu.

• void popup event menu ()

Populates the event-selection menu that drops from the "Event" button in the bottom row of the Pattern editor.

void popup_midibus_menu ()

Populates the MIDI Output buss pop-up menu.

void popup sequence menu ()

Populates the "set background sequence" menu (drops from the button that has some note-bars on it at the right of the second row of the top bar).

void popup_tool_menu ()

Sets up the pop-up menus that are brought up by pressing the Tools button, which shows a hammer image.

· void popup midich menu ()

Populates the MIDI Channel pop-up menu.

Gtk::Image * create_menu_image (bool state=false)

Sets the menu pixmap depending on the given state, where true is a full menu (black backgroun), and empty menu (gray background).

• bool timeout ()

Update the window after a time out, based on dirtiness and on playback progress.

void do_action (int action, int var)

Implements the actions brought forth from the Tools (hammer) button.

- void mouse_action (mouse_action_e action)
- void start playing ()
- void stop_playing ()
- · void change_focus (bool set_it=true)

Changes what perform and mainwid see as the "current sequence".

• void handle_close ()

Handles closing the sequence editor.

· void on realize ()

On realization, calls the base-class version, and connects the redraw timeout signal, timed at redraw_period_ms().

void on_set_focus (Widget *focus)

On receiving focus, attempt to tell mainwid that this sequence is now the current sequence.

bool on focus in event (GdkEventFocus *)

Implements the on-focus event handling.

• bool on_focus_out_event (GdkEventFocus *)

Implements the on-unfocus event handling.

bool on_delete_event (GdkEventAny *event)

Handles an on-delete event.

bool on_scroll_event (GdkEventScroll *ev)

Handles an on-scroll event.

• bool on_key_press_event (GdkEventKey *ev)

Handles a key-press event.

Private Attributes

- · friend segmenu
- · const int m initial zoom

Provides the initial zoom, used for restoring the original zoom using the 0 key.

• int m_zoom

Provides the zoom values: 1 2 3 4, and 1, 2, 4, 8, 16.

• int m_snap

Used in setting the snap-to value in pulses, of f = 1.

· int m_note_length

The default length of a note to be inserted by a right-left-click operation.

• int m_scale

Setting for the music scale, can now be saved with the sequence.

· int m chord

Setting for the current chord generation; not now saved with the sequence.

int m key

Setting for the music key, can now be saved with the sequence.

• int m_bgsequence

Setting for the background sequence, can now be saved with the sequence.

long m_measures

Provides the length of the sequence in measures.

• int m_ppqn

Holds a copy of the current PPQN for the sequence (and the entire MIDI file).

- int m_pp_whole
- int m_pp_eighth
- int m pp sixteenth
- sequence & m_seq

Holds a reference to the sequence that this window represents.

• Gtk::MenuBar * m_menubar

A number of user-interface objects for common.

• Gtk::Menu * m_menu_tools

The "hammer" tool button menu.

• Gtk::Menu * m_menu_zoom

• Gtk::Menu * m_menu_snap

Magnifying glass zoom menu.

Two-arrows grid-snap menu.

• Gtk::Menu * m menu note length

Notes menu for note length.

Gtk::Menu * m_menu_length

Pattern-length "bars" menu.

• Gtk::ToggleButton * m_toggle_transpose

Transpose toggle button.

```
• Gtk::Image * m_image_transpose
     Image for transpose button.
• Gtk::Menu * m menu midich
     MIDI channel DIN menu button.
• Gtk::Menu * m_menu_midibus
     MIDI output buss menu button.
• Gtk::Menu * m menu data
      "Event" button to select data.

    Gtk::Menu * m_menu_key

      "Music key" menu button.
• Gtk::Menu * m menu scale
      "Music scale" menu button.
• Gtk::Menu * m menu chords
      "Chords" menu button.
• Gtk::Menu * m menu sequences
      "Background sequence" button.
• Gtk::Menu * m_menu_bpm
     Beats/measure numerator menu.
• Gtk::Menu * m_menu_bw
     Beat-width denominator menu.
• Gtk::Button * m_button_lfo
• Ifownd * m Ifo wnd
• Gtk::Menu * m_menu_rec_vol
     Recording level "Vol" button.

    Gtk::Adjustment * m_vadjust

      Scrollbar and adjustment objects for horizontal and vertical panning.
• Gtk::Adjustment * m hadjust
     Horizontal motion scratchpad.
• Gtk::VScrollbar * m_vscroll_new
     Main vertical scroll-bar.

    Gtk::HScrollbar * m hscroll new

     Main horizontal scroll-bar.
• seqkeys * m_seqkeys_wid
     Handles the piano-keys part of the pattern-editor user-interface.

    seqtime * m_seqtime_wid

     Handles the time-line (bar or measures) part of the pattern-editor user-interface.
seqdata * m_seqdata_wid
     Handles the event-data part of the pattern-editor user-interface.
seqevent * m_seqevent_wid
     Handles the small event part of the pattern-editor user-interface, where events can be moved and added.
• seqroll * m_seqroll_wid
     Handles the piano-roll part of the pattern-editor user-interface.

    Gtk::Table * m table

     More user-interface elements.

    Gtk::VBox * m vbox

     Layout box for 3 h-boxes.

    Gtk::HBox * m hbox

      Topmost menu/text dialog row.

    Gtk::HBox * m hbox2

     Second row of buttons.
```

• Gtk::Button * m_button_undo

Undo-edit button.

• Gtk::Button * m_button_redo

Redo-edit button.

• Gtk::Button * m button quantize

Quantize-pattern button.

Gtk::Button * m button tools

Button for the Tools menu.

Gtk::Button * m button sequence

Button for Background pattern.

• Gtk::Entry * m_entry_sequence

Text for background pattern.

• Gtk::Button * m_button_bus

Button for MIDI Buss menu.

• Gtk::Entry * m_entry_bus

Text showing MIDI Buss name.

• Gtk::Button * m button channel

Button for the MIDI Channel.

• Gtk::Entry * m_entry_channel

Text for the MIDI Channel.

• Gtk::Button * m button snap

Button for the Grid-snap menu.

• Gtk::Entry * m_entry_snap

Text for selected Grid-snap.

• Gtk::Button * m_button_note_length

Button for Note-length menu.

• Gtk::Entry * m_entry_note_length

Text showing the Note-length.

• Gtk::Button * m_button_zoom

Button for the Zoom menu.

• Gtk::Entry * m entry zoom

Text for the selected Zoom.

• Gtk::Button * m_button_length

Button for pattern-length.

• Gtk::Entry * m_entry_length

Text for the pattern-length.

• Gtk::Button * m_button_key

Button for the Music Key.

• Gtk::Entry * m_entry_key

Text for selected Music Key.

• Gtk::Button * m_button_scale

Button for the Music Scale.

• Gtk::Entry * m_entry_scale

Text for the Music Scale.

Gtk::Button * m_button_chord

Button for the current Chord.

• Gtk::Entry * m_entry_chord

Text for the current Chord.

• Gtk::Tooltips * m_tooltips

Tooltip collector for dialog.

• Gtk::Button * m_button_data

Button for Event (data) menu.

• Gtk::Entry * m_entry_data

Text for the selected Event.

• Gtk::Button * m_button_bpm

Button for Beats/Measure menu.

Gtk::Entry * m_entry_bpm

Text for chosen Beats/Measure.

• Gtk::Button * m_button_bw

Button for Beat-Width menu.

Gtk::Entry * m_entry_bw

Text for chosen Beat-Width.

• Gtk::Button * m_button_rec_vol

Button for recording volume.

• Gtk::ToggleButton * m_toggle_play

Pattern-to-MIDI record button.

• Gtk::ToggleButton * m_toggle_record

MIDI-port-to-pattern button.

• Gtk::ToggleButton * m_toggle_q_rec

Quantized-record MIDI button.

• Gtk::ToggleButton * m_toggle_thru

MIDI-to-pattern-MIDI button.

• Gtk::Entry * m_entry_name

Name of the sequence.

midibyte m_editing_status

Indicates what MIDI event/status the data window currently editing.

midibyte m_editing_cc

Indicates what MIDI CC value the data window currently editing.

• bool m_have_focus

Indicates that the focus has already been changed to this sequence.

Static Private Attributes

• static int m_initial_snap

Static data members.

- static int m_initial_note_length
- static int m_initial_chord

Additional Inherited Members

12.61.1 Detailed Description

- perform
- · segroll
- · seqkeys
- seqdata
- seqtime
- · segevent
- sequence

This class has a metric ton of user-interface objects and other members.

12.61.2 Constructor & Destructor Documentation

12.61.2.1 segedit()

If provided, override the scale, key, and background-sequence with the values stored in the file with the sequence, if they are set to non-default values. This is a new feature.

Todo Offload most of the work into an initialization function like options does.

Todo Support the hightlight feature in one or both perfedit windows in the same way it is done in the mainwid.

Horizontal Gtk::Adjustment constructor: The initial value was 0 on a range from 0 to 1, with step and page increments of 1, and a page_size of 1. We can fix these values here, or create an h_adjustment() function similar to eventedit ::v_adjustment(), which first gets called in on_realize().

```
12.61.2.2 ~seqedit()

seq64::seqedit::~seqedit ( ) [virtual]
```

12.61.3 Member Function Documentation

It is passed to the seqroll, seqtime, seqdata, and seqevent objects, as well. This function doesn't check if the zoom will change, because this function might be used to initialize the zoom of the children.

The notation for zoom in the user-interface is in pixels:ticks, but I would prefer to use pulses/pixel (pulses per pixel). Oh well. Note that this value of zoom is saved to the "user" configuration file when Sequencer64 exit.

Parameters

The prospective zoom value to set. It is applied only if between the minimum and maximum allowed zoom values, inclusive. See the usr().min_zoom() and usr().max_zoom() function.

12.61.3.2 set_snap()

It is passed to the seqroll, seqevent, and sequence objects, as well.

The default initial snap is the default PPQN divided by 4, or the equivalent of a 16th note (48 ticks). The snap divisor is 192 * 4 / 48 or 16.

Parameters

s The prospective snap value to set. It is checked only to make sure it is greater than 0, to avoid a numeric exception.

12.61.3.3 set_note_length()

It is passed to the segroll object, as well.

Warning

Currently, we don't handle changes in the global PPQN after the creation of the menu. The creation of the menu hard-wires the values of note-length. To adjust for a new global PQN, we will need to store the original PPQN (m_original_ppqn = m_ppqn), and then adjust the notelength based on the new PPQN. For example if the new PPQN is twice as high as 192, then the notelength should double, though the text displayed in the "Note length" field should remain the same. However, we do adjust for a non-default PPQN at startup time.

Parameters

```
notelength | Provides the note length in units of MIDI pulses.
```

12.61.3.4 set_beats_per_bar()

12.61.3.5 set_beat_width()

12.61.3.6 set_transpose_image()

istransposable	If true, set the image to the "Transpose" icon. Otherwise, set it to the "Drum" (not]
	transposable) icon.	

12.61.3.7 set_rec_vol()

Parameters

recvol | The setting to be made, obtained from the recording-volume ("Vol") menu.

12.61.3.8 horizontal_adjust()

```
void seq64::seqedit::horizontal_adjust (
    double step ) [inline], [private]
```

A duplicate of the one in seqroll.

Parameters

step Provides the step value to use for adjusting the horizontal scrollbar. See gui_drawingarea_gtk2::scroll_hadjust() for more information.

12.61.3.9 vertical_adjust()

A near-duplicate of the one in seqroll.

Parameters

step Provides the step value to use for adjusting the vertical scrollbar. See gui_drawingarea_gtk2::scroll_vadjust() for more information.

12.61.3.10 horizontal_set()

value

The desired position. Mostly this is either 0.0 or 9999999.0 (an "infinite" value to select the start or end position.

12.61.3.11 vertical_set()

Parameters

value

The desired position. Mostly this is either 0.0 or 9999999.0 (an "infinite" value to select the start or end position.

12.61.3.12 set_measures()

Parameters

lim

Provides the sequence length, in measures.

12.61.3.13 apply_length()

There's an implicit "adjust-triggers = true" parameter used in sequence::set_length().

Then the seqroll, seqtime, seqdata, and seqevent objects are reset().

12.61.3.14 get_measures()

```
long seq64::seqedit::get_measures ( ) [private]
```

Todo Create a sequence::set_units() function or a sequence::get_measures() function to forward to.

12.61.3.15 set_midi_channel()

Should this change set the is-modified flag? Where should validation occur?

midichannel	The MIDI channel value to set.	
user_change	True if the user made this change, and thus has potentially modified the song.	1

12.61.3.16 set_midi_bus()

Should this change set the is-modified flag? Where should validation against the ALSA or JACK buss limits occur?

Also, it would be nice to be able to update this display of the MIDI bus in the field if we set it from the segmenu.

Parameters

bus	The buss value to set.	
user_chai	e True if the user made this cha	nge, and thus has potentially modified the song.

12.61.3.17 set_scale()

It is passed to the seqroll and seqkeys objects, as well. As a new feature, it is also passed to the sequence, so that it can be saved as part of the sequence data.

Note that the "initial value" for this parameter is a static variable that gets set to the new value, so that opening up another sequence causes the sequence to take on the new "initial value" as well. A feature, but should it be optional? Now it is, based on the setting of usr().global_seq_feature().

12.61.3.18 set_chord()

int key) [private]

It is passed to the sequence, so that it can be saved as part of the sequence data.

Note that the "initial value" for this parameter is a static variable that gets set to the new value, so that opening up another sequence causes the sequence to take on the new "initial value" as well. A feature, but should it be optional? Now it is, based on the setting of usr().global_seq_feature().

12.61.3.20 set_background_sequence()

As a new feature, it is also passed to the sequence, so that it can be saved as part of the sequence data, but only if less or equal to the maximum single-byte MIDI value, 127.

Note that the "initial value" for this parameter is a static variable that gets set to the new value, so that opening up another sequence causes the sequence to take on the new "initial value" as well. A feature, but should it be optional? Now it is, based on the setting of usr().global_seq_feature().

12.61.3.21 transpose_change_callback()

```
void seq64::seqedit::transpose_change_callback ( ) [private]
```

12.61.3.22 name_change_callback()

```
void seq64::seqedit::name_change_callback ( ) [private]
```

That name is the name the user has given to the sequence being edited.

12.61.3.23 play_change_callback()

```
void seq64::seqedit::play_change_callback ( ) [private]
```

12.61.3.24 record_change_callback()

```
void seq64::seqedit::record_change_callback ( ) [private]
```

Stazed:

Both record_change_callback() and thru_change_callback() will call set_sequence_input() for the same sequence. We only need to call it if it is not already set, if setting. And, we should not unset it if the m_toggle_thru->get_active() is true.

12.61.3.25 q_rec_change_callback()

```
void seq64::seqedit::q_rec_change_callback ( ) [private]
```

12.61.3.26 thru_change_callback()

```
void seq64::seqedit::thru_change_callback ( ) [private]
```

Stazed:

Both record_change_callback() and thru_change_callback() will call set_sequence_input() for the same sequence. We only need to call it if it is not already set, if setting. And, we should not unset it if the m_toggle_thru->get_active() is true.

This function uses the hardwired array c_controller_names.

Parameters

sta	tus	The current editing status.
cor	ntrol	The control value. However, we really need to validate it!

```
12.61.3.30 update_all_windows()
void seq64::seqedit::update_all_windows ( ) [private]

12.61.3.31 fill_top_bar()
void seq64::seqedit::fill_top_bar ( ) [private]
```

Note that, if a non-default title for the sequence is in force, then we immediately force the focus to the sequol "widget", so that the space bar can be used to control playback, instead of immediately erasing the name of the sequence. The following commented radio-buttons were a visual way to select the modes of note editing (select, draw, and grow). These can easily be done with the left mouse button, keystrokes, or some other tricks, though.

```
12.61.3.32 create_menus()
void seq64::seqedit::create_menus ( ) [private]
```

The first menu is the Zoom menu, represented in the pattern/sequence editor by a button with a magnifying glass. The values are "pixels to ticks", where "ticks" are actually the "pulses" of "pulses per quarter note". We would prefer the notation "n" instead of "1:n", as in "n pulses per pixel".

Note that many of the setups here could be loops through data structures. The Snap menu is actually the Grid Snap button, which shows two arrows pointing to a central bar. This menu somewhat duplicates the same menu in perfedit.

To reduce the amount of written code, we now use a static array to initialize some of the sequedit menu entries. 0 denotes the separator. This same setup is used to set up both the snap and note menu, since they are exactly the same. Saves a *lot* of code.

This menu lets one set the key of the sequence, and is brought up by the button with the "golden key" image on it.

This button shows a down around for the bottom half of the time signature. It's tooltip is "Time signature. Length of beat." But it is called bw, or beat width, in the code.

This menu is shown when pressing the button at the bottom of the window that has "Vol" as its label. Let's show the numbers as well to help the user. And we'll have to document this change.

This menu sets the scale to show on the panel, and the button shows a "staircase" image. See the c_music_scales enumeration defined in the globals module.

This section sets up two different menus. The first is m_menu_length. This menu lets one set the sequence length in bars. The second menu is the m_menu_bpm, or BPM, which here means "beats per measure" (not "beats per minute").

12.61.3.33 popup_menu()

12.61.3.34 popup_event_menu()

```
void seq64::seqedit::popup_event_menu ( ) [private]
```

This menu has a large number of items. I think they are filled in in code, but can also be loaded from \sim /.seq24usr. To be determined. Create the 8 sub-menus for the various ranges of controller changes, shown 16 per sub-menu.

12.61.3.35 popup_midibus_menu()

```
void seq64::seqedit::popup_midibus_menu ( ) [private]
```

The MIDI busses are obtained by getting the mastermidibus object, and iterating through the busses that it contains.

12.61.3.36 popup_sequence_menu()

```
void seq64::seqedit::popup_sequence_menu ( ) [private]
```

It is populated with an "Off" menu entry, and a second "[0]" menu entry that pulls up a drop-down menu of all of the patterns/sequences that are present in the MIDI file for screen-set 0. If more screensets have active sequences, then their screen-set number appears in the screen-set section of the menu.

Now, at present, we can only save background sequence numbers that are less than 128, which means the sequences from 0 to 127, or the first four screen sets. Higher sequences can be selected, but, right now, they cannot be saved. We'll probably fix that at some point, low priority.

```
12.61.3.37 popup_tool_menu()
void seq64::seqedit::popup_tool_menu ( ) [private]
```

This button shows three sub-menus that need to be filled in by this function. All the functions accessed here seem to be implemented by the do_action() function.

Note the new call to seqroll::follow_progress(). This allows the seqroll to pop to the next frame of events to continue to show the moving progress bar. Does this need to be an option? It only affects patterns longer than a measure or two, whatever the width of the seqroll window is. This is a new feature that is not in seq24.

What about seqtime? That doesn't change.

```
12.61.3.41 do_action()
```

Note that the push_undo() calls push all of the current events (in sequence::m_events) onto the stack (as a single entry).

```
12.61.3.42 mouse_action()
```

Similar to the same function in eventedit.

12.61.3.46 handle_close()

```
set

if true (the default value), indicates we want focus, otherwise we want to give up focus.

it
```

```
void seq64::seqedit::handle_close ( ) [private]
12.61.3.47 on_realize()
void seq64::seqedit::on_realize ( ) [private]
12.61.3.48 on_set_focus()
void seq64::seqedit::on_set_focus (
             Widget * focus ) [private]
Only works in certain circumstances.
12.61.3.49 on_focus_in_event()
bool seq64::seqedit::on_focus_in_event (
             GdkEventFocus * ) [private]
12.61.3.50 on_focus_out_event()
bool seq64::seqedit::on_focus_out_event (
             GdkEventFocus * ) [private]
12.61.3.51 on_delete_event()
bool seq64::seqedit::on_delete_event (
```

It tells the sequence to stop recording, tells the perform object's mastermidibus to stop processing input, and sets the sequence object's editing flag to false.

Warning

This function also calls "delete this"!

GdkEventAny * event) [private]

Returns

Always returns false.

```
12.61.3.52 on_scroll_event()
```

This handles moving the scroll wheel on a mouse or do a two-fingered scrolling action on a touchpad. If no modifier key is pressed, this moves the view up or down on the "notes" coordinate, showing different piano keys. This behavior is implemented in seqkeys::on scroll event(), and is called into play by returning false here.

If the Ctrl key is pressed, then the scrolling action causes the view to zoom in or out. This behavior is implemented here.

If the Shift key is pressed, then the scrolling action moves the view horizontally on the time-line (measures-line) of the piano roll. This behavior is implemented here.

```
12.61.3.53 on_key_press_event()
```

A number of new keystrokes are processed, so that we can lessen the reliance on the mouse and work a little faster.

```
Ctrl-W keypress. This keypress closes the sequence/pattern editor window by way of calling on_delete_event(). We could apply this convention to all the other windows.
z 0 Z zoom keys. "z" zooms out, "Z" (Shift-z) zooms in, and "0" resets the zoom to the default.
Page-Up and Page-Down. Moves up and down in the piano roll.
Home and End. Page to the top or the bottom of the piano roll.
Shift-Page-Up and Shift-Page-Down. Move left and right in the piano roll.
Shift-Home and Shift-End. Page to the start or the end of the piano roll.
Ctrl-Page-Up and Ctrl-Page-Down. Mirrors the zoom-in and zoom-out capabilities of scrolling up and down with the mouse while the Ctrl key is pressed.
```

The Keypad-End key is an issue on our ASUS "gaming" laptop. Whether it is seen as a "1" or an "End" key depends on an interaction between the Shift and the Num Lock key. Annoying, takes some time to get used to.

Change Note layk 2016-10-17 Issue #46. Undoing (ctrl-z) removes two instances of history. To reproduce this bug, if one makes three notes one at a time and presses ctrl-z once only the first one remains. Same goes for moving notes. This is due to this else-if statement where we call seqroll::on_key_press_event() making first removal. This if statement is never true and seqroll::on_key_press_event() is called again as Gtk::Window::on_key_press_event(), making another m_seq.pop_undo() in seqroll. Note that the code here was an (ill-advised) attempt to avoid the pattern title field from grabbing the initial keystrokes; better to just get used to clicking the piano roll first. Finally, fixing the undo bug also let's ctrl-page-up/page-down change the zoom. Lastly, we've removed the undo here... seqroll already handles both undo and redo keystrokes.

Change Note ca 2016-10-18 Issue #46. In addition to layk's fixes, we have to properly determine if we're inside the "Sequence Name" ("GtkEntry") field, as opposed to the "GtkDrawingArea" field, to avoid grabbing and using keystrokes intended for the text-entry field. We may have to rethink the whole seqroll vs. seqedit key-press process at some point, as this is a bit too tricky. Please note that the name "gtkmm__GtkEntry" likely applies only to GNU's C++ compiler, g++. This will be an issue in any port to Microsoft's C++ compiler.

Parameters

ev Provides the keystroke event to be handled.

Returns

Returns true if we handled the keystroke here. Otherwise, returns the value of Gtk::Window::on_key_press-_event(ev).

12.61.4 Field Documentation

12.61.4.1 segmenu

```
friend seq64::seqedit::seqmenu [private]
```

12.61.4.2 m_initial_snap

```
int seq64::seqedit::m_initial_snap [static], [private]
```

These items apply to all of the instances of seqedit, and are passed on to the following constructors:

- seqdata
- · seqevent
- · segroll
- · seqtime

The snap and note-length defaults would be good to write to the "user" configuration file. The scale and key would be nice to write to the proprietary section of the MIDI song. Or, even more flexibly, to each sequence, if that makes sense to do, since all tracks would generally be in the same key. Right, Charles Ives?

Note that, currently, that some of these "initial values" are modified, so that they are "contagious". That is, the next sequence to be opened in the sequence editor will adopt these values. This is a long-standing feature of Seq24, but strikes us as a bit surprising.

Change Note ca 2016-04-10 If we just double the PPQN, then the snap divisor becomes 32, and the snap interval is a 32nd note. We would like to keep it at a 16th note. We correct the snap ticks to the actual PPQN ratio.

12.61.4.3 m_initial_note_length

```
int seq64::seqedit::m_initial_note_length [static], [private]
```

12.61.4.4 m_initial_chord

```
int seq64::seqedit::m_initial_chord [static], [private]
```

12.61.4.5 m_initial_zoom

```
const int seq64::seqedit::m_initial_zoom [private]
```

```
12.61.4.6 m_zoom
int seq64::seqedit::m_zoom [private]
The value of zoom is the same as the number of pixels per tick on the piano roll.
12.61.4.7 m_snap
int seq64::seqedit::m_snap [private]
12.61.4.8 m_note_length
int seq64::seqedit::m_note_length [private]
12.61.4.9 m_scale
int seq64::seqedit::m_scale [private]
12.61.4.10 m_chord
int seq64::seqedit::m_chord [private]
12.61.4.11 m_key
int seq64::seqedit::m_key [private]
12.61.4.12 m_bgsequence
int seq64::seqedit::m_bgsequence [private]
12.61.4.13 m_measures
long seq64::seqedit::m_measures [private]
12.61.4.14 m_ppqn
int seq64::seqedit::m_ppqn [private]
12.61.4.15 m_pp_whole
int seq64::seqedit::m_pp_whole [private]
```

```
12.61.4.16 m_pp_eighth
int seq64::seqedit::m_pp_eighth [private]
12.61.4.17 m_pp_sixteenth
int seq64::seqedit::m_pp_sixteenth [private]
12.61.4.18 m_seq
sequence& seq64::seqedit::m_seq [private]
12.61.4.19 m_menubar
Gtk::MenuBar* seq64::seqedit::m_menubar [private]
Many of these are menu items, and are associated with buttons that, when pressed, bring up the menu for display
and selection of its entries. The top bar with menu buttons.
12.61.4.20 m_menu_tools
Gtk::Menu* seq64::seqedit::m_menu_tools [private]
12.61.4.21 m_menu_zoom
Gtk::Menu* seq64::seqedit::m_menu_zoom [private]
12.61.4.22 m_menu_snap
Gtk::Menu* seq64::seqedit::m_menu_snap [private]
12.61.4.23 m_menu_note_length
Gtk::Menu* seq64::seqedit::m_menu_note_length [private]
12.61.4.24 m_menu_length
Gtk::Menu* seq64::seqedit::m_menu_length [private]
12.61.4.25 m_toggle_transpose
Gtk::ToggleButton* seq64::seqedit::m_toggle_transpose [private]
```

```
12.61.4.26 m_image_transpose
Gtk::Image* seq64::seqedit::m_image_transpose [private]
12.61.4.27 m_menu_midich
Gtk::Menu* seq64::seqedit::m_menu_midich [private]
12.61.4.28 m_menu_midibus
Gtk::Menu* seq64::seqedit::m_menu_midibus [private]
12.61.4.29 m_menu_data
Gtk::Menu* seq64::seqedit::m_menu_data [private]
12.61.4.30 m_menu_key
Gtk::Menu* seq64::seqedit::m_menu_key [private]
12.61.4.31 m_menu_scale
Gtk::Menu* seq64::seqedit::m_menu_scale [private]
12.61.4.32 m_menu_chords
Gtk::Menu* seq64::seqedit::m_menu_chords [private]
12.61.4.33 m_menu_sequences
Gtk::Menu* seq64::seqedit::m_menu_sequences [private]
12.61.4.34 m_menu_bpm
Gtk::Menu* seq64::seqedit::m_menu_bpm [private]
12.61.4.35 m_menu_bw
Gtk::Menu* seq64::seqedit::m_menu_bw [private]
```

```
12.61.4.36 m_button_lfo
Gtk::Button* seq64::seqedit::m_button_lfo [private]
12.61.4.37 m_lfo_wnd
lfownd* seq64::seqedit::m_lfo_wnd [private]
12.61.4.38 m_menu_rec_vol
Gtk::Menu* seq64::seqedit::m_menu_rec_vol [private]
12.61.4.39 m_vadjust
Gtk::Adjustment* seq64::seqedit::m_vadjust [private]
Vertical position descriptor.
12.61.4.40 m_hadjust
Gtk::Adjustment* seq64::seqedit::m_hadjust [private]
12.61.4.41 m_vscroll_new
Gtk::VScrollbar* seq64::seqedit::m_vscroll_new [private]
12.61.4.42 m_hscroll_new
Gtk::HScrollbar* seq64::seqedit::m_hscroll_new [private]
12.61.4.43 m_seqkeys_wid
seqkeys* seq64::seqedit::m_seqkeys_wid [private]
This item draws the piano-keys at the left of the seqedit window.
12.61.4.44 m_seqtime_wid
seqtime* seq64::seqedit::m_seqtime_wid [private]
```

This is the location where the measure numbers and the END marker are shown.

```
12.61.4.45 m_seqdata_wid
seqdata* seq64::seqedit::m_seqdata_wid [private]
This is the area at the bottom of the window that shows value lines for the selected kinds of events.
12.61.4.46 m_seqevent_wid
seqevent* seq64::seqedit::m_seqevent_wid [private]
12.61.4.47 m_seqroll_wid
seqroll* seq64::seqedit::m_seqroll_wid [private]
12.61.4.48 m_table
Gtk::Table* seq64::seqedit::m_table [private]
These items provide a number of buttons and text-entry fields, as well as their layout. The layout table for editor.
12.61.4.49 m_vbox
Gtk::VBox* seq64::seqedit::m_vbox [private]
12.61.4.50 m_hbox
Gtk::HBox* seq64::seqedit::m_hbox [private]
12.61.4.51 m_hbox2
Gtk::HBox* seq64::seqedit::m_hbox2 [private]
12.61.4.52 m_button_undo
Gtk::Button* seq64::seqedit::m_button_undo [private]
12.61.4.53 m_button_redo
```

Gtk::Button* seq64::seqedit::m_button_redo [private]

```
12.61.4.54 m_button_quantize
Gtk::Button* seq64::seqedit::m_button_quantize [private]
12.61.4.55 m_button_tools
Gtk::Button* seq64::seqedit::m_button_tools [private]
12.61.4.56 m_button_sequence
Gtk::Button* seq64::seqedit::m_button_sequence [private]
12.61.4.57 m_entry_sequence
Gtk::Entry* seq64::seqedit::m_entry_sequence [private]
12.61.4.58 m button bus
Gtk::Button* seq64::seqedit::m_button_bus [private]
12.61.4.59 m_entry_bus
Gtk::Entry* seq64::seqedit::m_entry_bus [private]
12.61.4.60 m_button_channel
Gtk::Button* seq64::seqedit::m_button_channel [private]
12.61.4.61 m_entry_channel
Gtk::Entry* seq64::seqedit::m_entry_channel [private]
12.61.4.62 m button snap
Gtk::Button* seq64::seqedit::m_button_snap [private]
12.61.4.63 m_entry_snap
Gtk::Entry* seq64::seqedit::m_entry_snap [private]
```

```
12.61.4.64 m_button_note_length
Gtk::Button* seq64::seqedit::m_button_note_length [private]
12.61.4.65 m_entry_note_length
Gtk::Entry* seq64::seqedit::m_entry_note_length [private]
12.61.4.66 m_button_zoom
Gtk::Button* seq64::seqedit::m_button_zoom [private]
12.61.4.67 m_entry_zoom
Gtk::Entry* seq64::seqedit::m_entry_zoom [private]
12.61.4.68 m_button_length
Gtk::Button* seq64::seqedit::m_button_length [private]
12.61.4.69 m_entry_length
Gtk::Entry* seq64::seqedit::m_entry_length [private]
12.61.4.70 m_button_key
Gtk::Button* seq64::seqedit::m_button_key [private]
12.61.4.71 m_entry_key
Gtk::Entry* seq64::seqedit::m_entry_key [private]
12.61.4.72 m button scale
Gtk::Button* seq64::seqedit::m_button_scale [private]
12.61.4.73 m_entry_scale
Gtk::Entry* seq64::seqedit::m_entry_scale [private]
```

```
12.61.4.74 m_button_chord
Gtk::Button* seq64::seqedit::m_button_chord [private]
12.61.4.75 m_entry_chord
Gtk::Entry* seq64::seqedit::m_entry_chord [private]
12.61.4.76 m_tooltips
Gtk::Tooltips* seq64::seqedit::m_tooltips [private]
12.61.4.77 m_button_data
Gtk::Button* seq64::seqedit::m_button_data [private]
12.61.4.78 m_entry_data
Gtk::Entry* seq64::seqedit::m_entry_data [private]
12.61.4.79 m_button_bpm
Gtk::Button* seq64::seqedit::m_button_bpm [private]
12.61.4.80 m_entry_bpm
Gtk::Entry* seq64::seqedit::m_entry_bpm [private]
12.61.4.81 m button bw
Gtk::Button* seq64::seqedit::m_button_bw [private]
12.61.4.82 m_entry_bw
Gtk::Entry* seq64::seqedit::m_entry_bw [private]
12.61.4.83 m_button_rec_vol
Gtk::Button* seq64::seqedit::m_button_rec_vol [private]
```

```
12.61.4.84 m_toggle_play
Gtk::ToggleButton* seq64::seqedit::m_toggle_play [private]
12.61.4.85 m_toggle_record
{\tt Gtk::ToggleButton*} \  \, {\tt seq64::seqedit::m\_toggle\_record} \  \, [{\tt private}]
12.61.4.86 m_toggle_q_rec
Gtk::ToggleButton* seq64::seqedit::m_toggle_q_rec [private]
12.61.4.87 m_toggle_thru
Gtk::ToggleButton* seq64::seqedit::m_toggle_thru [private]
12.61.4.88 m_entry_name
Gtk::Entry* seq64::seqedit::m_entry_name [private]
12.61.4.89 m_editing_status
midibyte seq64::seqedit::m_editing_status [private]
12.61.4.90 m_editing_cc
midibyte seq64::seqedit::m_editing_cc [private]
12.61.4.91 m_have_focus
bool seq64::seqedit::m_have_focus [private]
```

12.62 seq64::seqevent Class Reference

Implements the piano event drawing area.

Inheritance diagram for seq64::seqevent:



Public Member Functions

• seqevent (perform &p, sequence &seq, int zoom, int snap, seqdata &seqdata_wid, Gtk::Adjustment &hadjust, int ppqn=SEQ64_USE_DEFAULT_PPQN)

Principal constructor.

virtual ∼seqevent ()

Let's provide a do-nothing virtual destructor.

· void reset ()

This function basically resets the whole widget as if it was realized again.

• void redraw ()

Adjusts the scrolling offset for ticks, updates the pixmap, and draws it on the window.

void set zoom (int zoom)

Sets zoom to the given value, and resets if the value ended up being changed.

void set_snap (int snap)

'Setter' function for member m_snap Simply sets the snap member.

void set_data_type (midibyte status, midibyte control)

Sets the status to the given parameter, and the CC value to the given optional control parameter, which defaults to 0.

void update_sizes ()

If the window is realized, this function creates a pixmap with window dimensions, the updates the pixmap, and queues up a redraw.

void draw_background ()

This function updates the background.

void draw_events_on_pixmap ()

This function fills the main pixmap with events.

void draw_pixmap_on_window ()

This function currently just gueues up a draw operation for the pixmap.

void draw_selection_on_window ()

Draw the selected events on the window.

void update_pixmap ()

Redraws the background pixmap on the main pixmap, then puts the events on.

Private Member Functions

virtual void force_draw ()

Forces a draw on the current drawable area of the window.

• int idle_redraw ()

Implements redraw while idling.

void x_to_w (int x1, int x2, int &x, int &w)

This function checks the mins / maxes.

· void drop_event (midipulse tick)

Drops (adds) an event at the given tick.

void draw_events_on (Glib::RefPtr< Gdk::Drawable > draw)

Draws events on the given drawable object.

· void start_paste ()

Starts a paste operation.

• void change_horz ()

Changes the horizontal scrolling offset for ticks, then updates the pixmap and forces a redraw.

void convert x (int x, midipulse &tick)

Takes the screen x coordinate, multiplies it by the current zoom, and returns the tick value in the given parameter.

void convert_t (midipulse tick, int &x)

Converts the given tick value to an x corrdinate, based on the zoom, and returns it via the second parameter.

void snap y (int &y)

This function performs a 'snap' on y.

void snap_x (int &x)

This function performs a 'snap' on x.

• void on_realize ()

Implements the on-realize callback.

bool on_expose_event (GdkEventExpose *ev)

Implements the on-expose event callback.

bool on_button_press_event (GdkEventButton *ev)

Implements the on-button-press event callback.

bool on_button_release_event (GdkEventButton *ev)

Implements the on-button-release event callback.

bool on_motion_notify_event (GdkEventMotion *ev)

Implements the on-motion-notify event callback.

bool on focus in event (GdkEventFocus *)

Responds to a focus event by setting the HAS_FOCUS flag.

bool on_focus_out_event (GdkEventFocus *)

Responds to a unfocus event by resetting the HAS FOCUS flag.

bool on_key_press_event (GdkEventKey *p0)

Implements the key-press event callback function.

void on_size_allocate (Gtk::Allocation &)

Implements the on-size-allocate event callback.

Private Attributes

FruitySeqEventInput m fruity interaction

Provides the mouse-handling paradigm for the fruity interaction.

Seq24SeqEventInput m_seq24_interaction

Provides the normal mouse-handling for Sequencer64.

• sequence & m_seq

Provides a reference to the sequence whose data is represented in this sequent object.

• int m zoom

Zoom setting, means that one pixel == m_zoom ticks.

int m_snap

The grid-snap setting for the event bar grid.

• int m_ppqn

The value to use for the PPQN for this sequence.

GdkRectangle m_old

Used in drawing the event selection in the thing event row.

• GdkRectangle m_selected

Used in moving and pasting the selected events in the thin event row.

int m_scroll_offset_ticks

Provides the offset of the ticks in the event view based on where the scroll-bar has moved the view "window".

int m_scroll_offset_x

Provides the offset of the pixels in the event view based on where the scroll-bar has moved the view "window".

· seqdata & m_seqdata_wid

The data view that parallels this event view.

bool m_selecting

Used when highlighting a bunch of events.

· bool m moving init

Used externally by the fruityseq and seq24seq modules, to initialize the act of moving events.

bool m moving

Indicates that this pane is in the act of moving a selection.

bool m_growing

Used externally by the fruityseq and seq24seq modules, when growing the event duration.

· bool m_painting

Used externally by the fruityseq and seq24seq modules, in painting the selected events.

• bool m_paste

Indicates that we've selected some events and are in paste mode.

int m_move_snap_offset_x

Used externally by the fruityseq and seq24seq modules, in snapping.

• midibyte m_status

Indicates what is the data window currently editing.

• midibyte m_cc

Indicates what is the data window currently editing.

Friends

- struct FruitySeqEventInput
- struct Seq24SeqEventInput

Additional Inherited Members

12.62.1 Constructor & Destructor Documentation

12.62.1.1 seqevent()

```
seq64::seqevent::seqevent (
    perform & p,
    sequence & seq,
    int zoom,
    int snap,
    seqdata & seqdata_wid,
    Gtk::Adjustment & hadjust,
    int ppqn = SEQ64_USE_DEFAULT_PPQN )
```

Parameters

р	The "parent" perform object controlling all of the sequences.
seq	The current sequence operated on by this object.
zoom	The initial zoom value.
snap	The initial snap value.
seqdata_wid	The data pane that this event pane is associated with.
hadjust	The horizontal scroll-bar.
ppqn	The initial PPQN value.

12.62.1.2 ∼seqevent()

```
\label{eq:continuous} \mbox{virtual seq64::seqevent::} \sim \mbox{seqevent ( ) [inline], [virtual]}
```

12.62.2 Member Function Documentation

Parameters

z The desired zoom value, assumed to be validated already. See the seqedit::set_zoom() function.

12.62.2.4 set_snap()

The parameter is not validated.

12.62.2.5 set_data_type()

Then redraws.

Parameters

status	The status/event byte to set. For example, EVENT_NOTE_ON and EVENT_NOTE off. This byte should have the channel nybble cleared.
control	The MIDI CC byte to set.

```
12.62.2.6 update_sizes()

void seq64::seqevent::update_sizes ( )

This ends up filling the background with dotted lines, etc.
```

```
12.62.2.7 draw_background()
```

```
void seq64::seqevent::draw_background ( )
```

It sets the foreground to white, draws the rectangle, in order to clear the pixmap. The build-time option SEQ64← _SOLID_PIANOROLL_GRID causes solid lines to be drawn, in gray, instead of dotted black lines, for a smoother look.

Also, as a trial option, if the current data type is EVENT_NOTE_ON, EVENT_NOTE_OFF, and EVENT_AFTER TOUCH, we draw the background in light grey to remind the user that there are issues in copying or moving these events around (unlinked) by themselves.

```
12.62.2.8 draw_events_on_pixmap()

void seq64::seqevent::draw_events_on_pixmap ()

12.62.2.9 draw_pixmap_on_window()

void seq64::seqevent::draw_pixmap_on_window ()

Old comments:

It then tells event to do the same. We changed something on this window, and chances are we need to update the event widget as well and update our velocity window.

12.62.2.10 draw_selection_on_window()

void seq64::seqevent::draw_selection_on_window ()

12.62.2.11 update_pixmap()

void seq64::seqevent::update_pixmap ()

12.62.2.12 force_draw()
```

void seq64::seqevent::force_draw () [private], [virtual]

Reimplemented from seq64::gui_drawingarea_gtk2.

Generated by Doxygen

12.62.2.13 idle_redraw()

```
int seq64::seqevent::idle_redraw ( ) [private]
```

Who calls this routine? Probably the default timer routine, but not sure.

Returns

Always returns true.

12.62.2.14 x_to_w()

Then it fills in x and the width.

Parameters

	x1	The "left" x value.
	x2	The "right" x value.
out	Х	The destination for the converted x value.
out	W	The destination for the converted width value.

12.62.2.15 drop_event()

It sets the first byte properly for after-touch, program-change, channel-pressure, and pitch-wheel. The type of event is determined by m_s tatus.

Parameters

tick The destination time (division, pulse, tick) for the event to be dropped at.

12.62.2.16 draw_events_on()

Very similar to seqdata::draw_events_on().

drawable	The given drawable object.	
----------	----------------------------	--

12.62.2.17 start_paste()

```
void seq64::seqevent::start_paste ( ) [private]
```

It gets the clipboard box that selected elements are in, makes a coordinate conversion, and then, sets the m_{\leftarrow} selected rectangle to hold the (x,y,w,h) of the selected events.

12.62.2.18 change_horz()

```
void seq64::seqevent::change_horz ( ) [private]
```

Very similar to seqroll::change_horz(). Basically identical to seqdata::change_horz().

12.62.2.19 convert_x()

Why not just return it normally?

Parameters

	Х	The x (pixel) value to convert.
out	tick	The destination for the converted x value.

12.62.2.20 convert_t()

Why not just return it normally?

Parameters

	tick	The tick (pulse) value to convert.
out	X	The destination for the converted tick value.

12.62.2.21 snap_y()

Parameters

01	ıt	у	The return parameter for the conversion. Why not just return the value?	_
----	----	---	---	---

12.62.2.22 snap_x()

- snap = number pulses to snap to
- m_zoom = number of pulses per pixel
- Therefore snap / m_zoom = number of pixels to snap to.

Parameters

```
out x The output destination for the snapped x value.
```

12.62.2.23 on_realize()

```
void seq64::seqevent::on_realize ( ) [private]
```

It calls the base-class version, and then allocates additional resource not allocated in the constructor. Finally, it connects up the change_horz function.

12.62.2.24 on_expose_event()

Parameters

```
ev The expose event.
```

12.62.2.25 on_button_press_event()

It distinguishes between the Seq24 and Fruity varieties of mouse interaction.

Odd. In the legacy code, each case fell through to the next case to the "default" case! We will assume for now that this is incorrect.

Note that returning "true" from a Gtkmm event-handler stops the propagation of the event to higher-level widgets. The Fruity and Seq24 event handlers return true, always. In the legacy code, though, the fall-through code caused false to be returned, always. Not sure what effect this had. Added some fixes, but then commented them out until better testing can be done.

Parameters

```
ev The button event.
```

Returns

Returns true if the button-press was handled.

12.62.2.26 on_button_release_event()

It distinguishes between the Seq24 and Fruity varieties of mouse interaction.

Odd. The fruity case fell through to the Seq24 case. We will assume for now that this is correct. Added some fixes, but then commented them out until better testing can be done.

Parameters

```
ev The button event.
```

Returns

Returns true if the button-press was handled.

12.62.2.27 on_motion_notify_event()

It distinguishes between the Seq24 and Fruity varieties of mouse interaction.

Odd. The fruity case fell through to the Seq24 case. We will assume for now that this is correct. Added some fixes, but then commented them out until better testing can be done.

Parameters

Returns

Returns true if the motion-event was handled.

```
12.62.2.28 on_focus_in_event()
```

Parameter "ev" is the focus event, unused.

Returns

Always returns false.

12.62.2.29 on_focus_out_event()

Parameter "ev" is the focus event, unused.

Returns

Always returns false.

12.62.2.30 on_key_press_event()

It handles deleted a selection via the Backspace or Delete keys, cut via Ctrl-X, copy via Ctrl-C, paste via Ctrl-V, and undo via Ctrl-Z.

Would be nice to provide redo functionality via Ctrl-Y. :-)

Parameters

```
ev The key-press event.
```

Returns

Returns true if an event was handled. Only some of the handled events also cause the perform modification flag to be set as a side-effect.

12.62.2.31 on_size_allocate()

The m_window_x and m_window_y values are set to the allocation width and height, respectively.

Parameters

```
a The allocation to be processed.
```

12.62.3 Friends And Related Function Documentation

12.62.3.1 FruitySeqEventInput

```
friend struct FruitySeqEventInput [friend]
```

12.62.3.2 Seq24SeqEventInput

```
friend struct Seq24SeqEventInput [friend]
```

12.62.4 Field Documentation

12.62.4.1 m_fruity_interaction

```
FruitySeqEventInput seq64::seqevent::m_fruity_interaction [private]
```

Why should we need both at the same time? Just load the one that is specified in the configuration.

```
12.62.4.2 m_seq24_interaction
```

```
Seq24SeqEventInput seq64::seqevent::m_seq24_interaction [private]
```

```
12.62.4.3 m_seq
```

```
sequence& seq64::seqevent::m_seq [private]
```

12.62.4.4 m_zoom

```
int seq64::seqevent::m_zoom [private]
```

12.62.4.5 m_snap

```
int seq64::seqevent::m_snap [private]
```

Same meaning as for the piano roll. This value is the denominator of the note size used for the snap.

```
12.62.4.6 m_ppqn
int seq64::seqevent::m_ppqn [private]
Used in snap and zoom scaling.
12.62.4.7 m_old
GdkRectangle seq64::seqevent::m_old [private]
12.62.4.8 m_selected
GdkRectangle seq64::seqevent::m_selected [private]
12.62.4.9 m_scroll_offset_ticks
int seq64::seqevent::m_scroll_offset_ticks [private]
12.62.4.10 m_scroll_offset_x
int seq64::seqevent::m_scroll_offset_x [private]
Set to m_scroll_offset_ticks divided by m_zoom.
12.62.4.11 m_seqdata_wid
seqdata& seq64::seqevent::m_seqdata_wid [private]
12.62.4.12 m_selecting
bool seq64::seqevent::m_selecting [private]
12.62.4.13 m_moving_init
bool seq64::seqevent::m_moving_init [private]
12.62.4.14 m_moving
bool seq64::seqevent::m_moving [private]
```

WARNING: This operation seems to have a bug. It makes the events very very long. This bug exists in Seq24.

Generated by Doxygen

```
12.62.4.15 m_growing
bool seq64::seqevent::m_growing [private]
Does growing work in this view? Need to do some better testing.
12.62.4.16 m_painting
bool seq64::seqevent::m_painting [private]
12.62.4.17 m_paste
bool seq64::seqevent::m_paste [private]
12.62.4.18 m_move_snap_offset_x
int seq64::seqevent::m_move_snap_offset_x [private]
12.62.4.19 m_status
midibyte seq64::seqevent::m_status [private]
The current status/event byte.
12.62.4.20 m_cc
```

The current MIDI CC value.

midibyte seq64::seqevent::m_cc [private]

12.63 seq64::seqkeys Class Reference

This class implements the left side piano of the pattern/sequence editor.

Inheritance diagram for seq64::seqkeys:



Public Member Functions

• seqkeys (sequence &seq, perform &p, Gtk::Adjustment &vadjust)

Principal constructor.

virtual ∼seqkeys ()

Let's provide a do-nothing virtual destructor.

void set scale (int scale)

Sets the musical scale, then resets.

void set key (int key)

Sets the musical key, then resets.

void set_hint_key (int key)

Sets a key to grey so that it can serve as a scale hint.

void set_hint_state (bool state)

Sets the hint state to the given value.

Private Member Functions

virtual void force_draw ()

Forces a draw operation on the whole window.

void set listen button press (GdkEventButton *ev)

Sneaky accessors for the segroll friend.

- void set_listen_button_release (GdkEventButton *ev)
- void set_listen_motion_notify (GdkEventMotion *ev)
- · void draw_area ()

Draws the updated pixmap on the drawable area of the window where the keys' location is hardwired.

void update pixmap ()

Updates the pixmaps to prepare it for the next draw operation.

void convert_y (int y, int ¬e)

Takes the screen y coordinate, and returns the note value in the second parameter.

void draw_key (int key, bool state)

Draws the given key according to the given state.

void change_vert ()

Changes the y offset of the scrolling, and the forces a draw.

- void update_sizes ()
- void reset ()

Resetting the keys view updates the pixmap and queues up a draw operation.

bool is_black_key (int key) const

Detects a black key.

• void on_realize ()

Implements the on-realize event.

bool on_expose_event (GdkEventExpose *ev)

Implements the on-expose event, by drawing on the window.

bool on_button_press_event (GdkEventButton *ev)

Implements the on-button-press event callback.

• bool on_button_release_event (GdkEventButton *ev)

Implements the on-button-release event callback.

bool on_motion_notify_event (GdkEventMotion *p0)

Implements the on-motion-notify event handler.

bool on_enter_notify_event (GdkEventCrossing *p0)

Implements the on-enter notification event handler.

bool on_leave_notify_event (GdkEventCrossing *p0)

Implements the on-leave notification event handler.

bool on_scroll_event (GdkEventScroll *ev)

Implements the on-scroll-event notification event handler.

• void on_size_allocate (Gtk::Allocation &)

Implements the on-size-allocation notification event handler.

Private Attributes

• sequence & m_seq

The sequence object that the keys pane will be using.

int m_scroll_offset_key

Provides the value of the current top key in the keys pane.

· int m_scroll_offset_y

Provides the value of the current top key in the keys pane in units of relative pixels.

• bool m_hint_state

Indicates if a piano key is set to indicate where on the pitch scale the mouse cursor is sitting.

int m_hint_key

Indicates the current y-value of the mouse pointer in units of key value.

bool m_keying

Set to true while the left mouse button is being pressed.

• int m_keying_note

The note to be played when selected in the seqkeys pane.

• int m scale

This member holds the scale value for the musical scale for the current edit of the sequence.

· int m key

This member holds the key value for the musical key for the current edit of the sequence.

• bool m_show_octave_letters

The default value is to show the octave letters on the vertical virtual keyboard.

Friends

- · class segroll
- class FruitySeqRollInput

Additional Inherited Members

12.63.1 Detailed Description

Note the friends of this class, seqroll and FruitySeqRollInput. Where is Seq24SeqRollInput? Gone. It has been folded back into seqroll.

12.63.2 Constructor & Destructor Documentation

12.63.2.1 seqkeys()

Parameters

seq	Provides the sequence object to which this seqkeys pane is associated.
р	Provides the performance object to which this seqkeys pane (and all sequences) are associated.
vadjust	The range object for the vertical scrollbar linked to the position in the seqkeys pane.

```
12.63.2.2 \sim seqkeys()
```

```
virtual seq64::seqkeys::\simseqkeys ( ) [inline], [virtual]
```

12.63.3 Member Function Documentation

```
12.63.3.1 set_scale()
```

This function is called by the sequedit class.

Parameters

scale The musical scale va	alue to be set.
----------------------------	-----------------

12.63.3.2 set_key()

Parameters

key The musical key value to be set.

12.63.3.3 set_hint_key()

If m_hint_state is true, the key is drawn (again).

Parameters

key The key value to set the hint-key to.

12.63.3.4 set_hint_state()

```
void seq64::seqkeys::set_hint_state (
          bool state )
```

Parameters

state Provides the value for hinting, where true == on, false == off.

```
12.63.3.5 force_draw()
```

```
void seq64::seqkeys::force_draw ( ) [private], [virtual]
```

Unlike most other overridden versions of force draw(), this one does not call the base-class version.

Reimplemented from seq64::gui drawingarea gtk2.

```
12.63.3.6 set_listen_button_press()
```

From the stazed code.

Parameters

ev The event to be forwarded from the seqroll.

12.63.3.7 set listen_button_release()

void seq64::seqkeys::update_pixmap () [private]

This function draws the keys, which range from 0 to 127 (SEQ64_MIDI_COUNT_MAX - 1 = c_num_keys - 1). Every octave, a key letter and number (e.g. "C4") is shown. The letter is adjusted to match the current scale (e.g. "C4").

We want to support an option to show the key number rather than the note letter/number combination, and perhaps to toggle between them. The current difficulty is that the fonts used are just a little to high to fit within the vertical limits of each key. We really don't want to change the vertical size at this time, so we just print every other note value.

Also note that this algorithm draws from the top down, so we have to account for that.

12.63.3.11 convert_y()

Parameters

	У	The y (vertical) screen coordinate to convert.	
out	note	The destination for the note calculation. This would be better as a return value.	

12.63.3.12 draw_key()

It accounts for the black keys and the white keys, and for the highlighting of the active key.

Parameters

key	The key to be drawn.	
state	How the key is to be drawn, where false == normal, true == grayed. A key is greyed when the mouse	
	cursor is at the same vertical location on the piano as the key.	

12.63.3.13 change_vert()

```
void seq64::seqkeys::change_vert ( ) [private]
```

Weird, in seq24 and here, the following was used, completely by accident! We fixed it, but must beware!

```
m_scroll_offset_y = m_scroll_offset_key * c_key_y, // comma operator!!!
force_draw();
```

12.63.3.14 update_sizes()

```
void seq64::seqkeys::update_sizes ( ) [private]
```

12.63.3.15 reset()

```
void seq64::seqkeys::reset ( ) [private]
```

12.63.3.16 is_black_key()

Parameters

Returns

Returns true if the key is black (value 1, 3, 6, 8, or 10).

```
12.63.3.17 on_realize()
void seq64::seqkeys::on_realize ( ) [private]
```

Call the base-class version and then allocates resources that could not be allocated in the constructor. It connects the change_vert() function and then calls it.

```
12.63.3.18 on_expose_event()
```

```
bool seq64::seqkeys::on_expose_event (
    GdkEventExpose * ev ) [private]
```

Parameters

```
ev The expose-event object.
```

12.63.3.19 on_button_press_event()

It handles the left and right buttons. The left button, pressed on the piano keyboard, causes m_keying to be set to true, and the given note to play. The right button toggles the note display between letter/number and MIDI note number.

Parameters

```
ev The mouse-button event to use.
```

Returns

Always returns true.

12.63.3.20 on_button_release_event()

It currently handles only the left button, and only if m_keying is true.

This function is used after pressing on one of the keys on the left-side piano keyboard, to make it play, and turns off the playing of the note.

Parameters

```
ev The button-event.
```

Returns

Always returns true.

12.63.3.21 on_motion_notify_event()

This allows rolling down the keyboard, playing the notes one-by-one.

Parameters

```
p0 The motion event.
```

Returns

Always returns false.

12.63.3.22 on_enter_notify_event()

This greys the current key.

12.63.3.23 on_leave_notify_event()

This un-greys the current key and stops playing the note.

12.63.3.24 on_scroll_event()

Note that there is no usage of the modifier keys (e.g. Shift or Ctrl). Compare this function to seqedit::on_scroll_\cdot event().

Parameters

ev Provides the direction of the scroll event.

Returns

Always returns true.

12.63.3.25 on_size_allocate()

Parameters

all Provies the allocation and its width and height.

12.63.4 Friends And Related Function Documentation

```
12.63.4.1 segroll
```

```
friend class seqroll [friend]
```

12.63.4.2 FruitySeqRollInput

```
friend class FruitySeqRollInput [friend]
```

12.63.5 Field Documentation

```
12.63.5.1 m_seq
```

```
sequence& seq64::seqkeys::m_seq [private]
```

12.63.5.2 m_scroll_offset_key

```
int seq64::seqkeys::m_scroll_offset_key [private]
```

Modified in change_vert().

12.63.5.3 m_scroll_offset_y

```
int seq64::seqkeys::m_scroll_offset_y [private]
```

Modified in change_vert().

```
12.63.5.4 m_hint_state
```

```
bool seq64::seqkeys::m_hint_state [private]
```

12.63.5.5 m_hint_key

```
int seq64::seqkeys::m_hint_key [private]
```

12.63.5.6 m_keying

```
bool seq64::seqkeys::m_keying [private]
```

Used in playing the sound for each note as it is clicked in the seqkeys pane.

12.63.5.7 m_keying_note

```
int seq64::seqkeys::m_keying_note [private]
```

12.63.5.8 m_scale

```
int seq64::seqkeys::m_scale [private]
```

12.63.5.9 m_key

```
int seq64::seqkeys::m_key [private]
```

12.63.5.10 m_show_octave_letters


```
bool seq64::seqkeys::m_show_octave_letters [private]
```

If false, then the MIDI key numbers are shown instead. This is a new feature of Sequencer64.

12.64 seq64::seqmenu Class Reference

This class handles the right-click menu of the sequence slots in the pattern window.

Inheritance diagram for seq64::seqmenu:



Public Member Functions

seqmenu (perform &a_p)

Principal constructor.

virtual ∼seqmenu ()

Provides a rote base-class destructor.

• int current_seq () const

'Getter' function for member m_current_seq We're changing the name, so that "seq" indicates an integer by (an imperfect) convention.

· bool is modified () const

'Getter' function for member m_modified

Protected Member Functions

void current seq (int seq)

'Setter' function for member m_current_seq

• void set_edit_sequence (int seqnum)

'Setter' function for member m_edit_sequence Pass in -1 to disable the edit-sequence number.

void unset_edit_sequence (int seqnum)

'Setter' function for member m_edit_sequence Disable the edit-sequence number if it matches the parameter.

bool is edit sequence (int seqnum) const

'Getter' function for member m_edit_sequence Tests the parameter against m_edit_sequence.

· void is modified (bool flag)

'Setter' function for member m_modified

• sequence * get_current_sequence () const

'Getter' function for member m_mainperf.get_sequence(current_seq()) This call is used many, many times, and well worth wrapping.

sequence * get_sequence (int seqnum) const

Forwards the get-sequence call to the perform object.

• bool is_current_seq_active () const

Forwards the is-sequence-active check to the perform object.

• bool is_current_seq_in_edit () const

Forwards the is-sequence-in-edit check to the perform object.

• void new current sequence ()

Forwards the new-current-sequence call to the perform object.

void new_sequence (int seqnum)

Forwards the new-sequence call to the perform object.

• void delete_current_sequence ()

Forwards the delete-sequence call to the perform object.

void toggle_current_sequence ()

Forwards the sequence-playing-toggle call to the perform object.

void popup_menu ()

This function sets up the pattern menu entries.

void seq_edit ()

This menu callback launches the sequence-editor (pattern editor) window.

void seq_event_edit ()

This menu callback launches the new event editor window.

virtual void seq_set_and_edit (int seqnum)

Sets the current sequence and then acts as if the user had clicked on its slot.

virtual void seq_set_and_eventedit (int seqnum)

Sets the current sequence and then acts as if the user had right-clicked on its slot and selected "Event Edit".

Private Member Functions

- virtual void redraw (int a sequence)=0
- void seq_new ()

This function sets the new sequence into the perform object, a bit prematurely, though.

void seq_copy ()

Copies the selected (current) sequence to the clipboard sequence.

void seq_cut ()

Deletes the selected (current) sequence and copies it to the clipboard sequence, if it is not in edit mode.

void seq_paste ()

Pastes the sequence clipboard into the current sequence, if the current sequence slot is not active.

void seq_clear_perf ()

If the current sequence is active, this function pushes a trigger undo in the main perform object, clears its sequence triggers for the current sequence, and sets the dirty flag of the sequence.

void set_bus_and_midi_channel (int a_bus, int a_ch)

Sets up the bus, MIDI channel, and dirtiness flag of the current sequence in the main perform object, as per the give parameters.

• void set_transposable (bool flag)

Sets the "is-transposable" flag of the current sequence.

void mute_all_tracks ()

Mutes all tracks in the main perform object.

void unmute_all_tracks ()

Unmutes all tracks in the main perform object.

void toggle_all_tracks ()

Toggles the mute-status of all tracks in the main perform object.

• void on_realize ()

Private Attributes

• Gtk::Menu * m_menu

The menu to pop up when the right-click action is used either on a mainwid pattern slot or on a perfedit pattern name.

· perform & m mainperf

Provides a reference to the central (non-UI) object involved in managing a song and performance.

· sequence m_clipboard

Holds a copy of data concerning a sequence, which can then be pasted into another pattern slot.

seqedit * m_seqedit

Points to the latest sequdit object, if created.

• eventedit * m_eventedit

Points to the latest eventedit object, if created.

int m_current_seq

References the current sequence by sequence number.

bool m_modified

Indicates if a sequence has been created.

Friends

· class mainwnd

12.64.1 Detailed Description

It is an abstract base class.

12.64.2 Constructor & Destructor Documentation

12.64.2.1 segmenu()

```
seq64::seqmenu::seqmenu ( perform \& p )
```

Apart from filling in some of the members, this function initializes the clipboard, so that we don't get a crash on a paste with no previous copy.

Parameters

p The main performance object representing the whole MIDI song.

12.64.2.2 ∼seqmenu()

```
seq64::seqmenu::~seqmenu ( ) [virtual]
```

A rote destructor.

This is necessary in an abstraction base class.

If we determine that we need to delete the m_seqedit pointer, we can do it here. But that is not likely, because we can have many new seqedit objects in play, because we can edit many at once.

12.64.3 Member Function Documentation

```
12.64.3.4 set_edit_sequence()
void seq64::seqmenu::set_edit_sequence (
             int seqnum ) [inline], [protected]
Now a pass-along to the perform object.
12.64.3.5 unset_edit_sequence()
void seq64::seqmenu::unset_edit_sequence (
             int seqnum ) [inline], [protected]
12.64.3.6 is_edit_sequence()
bool seq64::seqmenu::is_edit_sequence (
              int seqnum ) const [inline], [protected]
Returns true if that member is not -1, and the parameter matches it. Now a pass-along to the perform object.
12.64.3.7 is_modified() [2/2]
void seq64::seqmenu::is_modified (
             bool flag ) [inline], [protected]
12.64.3.8 get_current_sequence()
sequence* seq64::seqmenu::get_current_sequence ( ) const [inline], [protected]
12.64.3.9 get_sequence()
sequence* seq64::seqmenu::get_sequence (
              int seqnum ) const [inline], [protected]
12.64.3.10 is_current_seq_active()
bool seq64::seqmenu::is_current_seq_active ( ) const [inline], [protected]
12.64.3.11 is_current_seq_in_edit()
bool seq64::seqmenu::is_current_seq_in_edit ( ) const [inline], [protected]
12.64.3.12 new_current_sequence()
void seq64::seqmenu::new_current_sequence ( ) [inline], [protected]
```

12.64.3.13 new_sequence()

12.64.3.15 toggle_current_sequence()

```
void seq64::seqmenu::toggle_current_sequence ( ) [inline], [protected]
```

12.64.3.16 popup_menu()

```
void seq64::seqmenu::popup_menu ( ) [protected]
```

It also sets up the pattern popup menu entries that are used in mainwid. Note that, for the selected sequence, the "Edit" and "Event Edit" menu entries are not included if a pattern editor or event editor is already running. The new event editor seems to create far-reaching problems that we do not yet understand, so it is now possible to disable it at build time. We have mitigated most of those problems by not allowing both a seq_edit() and a seq_event_edit() at the same time.

12.64.3.17 seq_edit()

```
void seq64::seqmenu::seq_edit ( ) [protected]
```

If it is already open for that sequence, this function just raises it.

Note that the m segedit member to which we save the new pointer is currently there just to avoid a compiler warning.

Also, if a new sequences is created, we set the m_modified flag to true, even though the sequence might later be deleted. Too much modification to keep track of!

An oddity is that calling show_all() here does not work unless the seqedit() constructor makes its show_all() call.

12.64.3.18 seq_event_edit()

```
void seq64::seqmenu::seq_event_edit ( ) [protected]
```

If it is already open for that sequence, this function just raises it.

Note that the m_eventedit member to which we save the new pointer is currently there just to avoid a compiler warning.

This menu entry is available only if the selected sequence is active. That is, if the sequence has already been created.

An oddity is that we need the show_all() call here in order to see the dialog. A situation different from that for sequdit! However, now it doesn't seem to be needed, and we have put it back into the eventedit constructor.

12.64.3.19 seq_set_and_edit()

How do we account for the current screenset? It might not matter if the mute/unmute keystrokes were designed to work only with the current screenset.

Parameters

seqnum	The number of the sequence to edit.
--------	-------------------------------------

Reimplemented in seq64::mainwid.

12.64.3.20 seg set and eventedit()

```
void seq64::seqmenu::seq_set_and_eventedit (
    int seqnum ) [protected], [virtual]
```

Parameters

seqnum	The number of the sequence to event-edit.
--------	---

Reimplemented in seq64::mainwid.

12.64.3.21 redraw()

Implemented in seq64::mainwid, and seq64::perfnames.

12.64.3.22 seq_new()

```
void seq64::seqmenu::seq_new ( ) [private]
```

For one thing, if current_seq() is either a -1 or is greater than the maximum allowed sequence number, perform :: is_active() will return false, and we have no idea whether the sequence is not active or the sequence number is just invalid. So we need to check the pointer we got before trying to use it.

```
12.64.3.23 seq_copy()
```

```
void seq64::seqmenu::seq_copy ( ) [private]
```

We use a more appropriate function than operator =() here: sequence::partial_assign().

Todo Can be offloaded to a perform member function that accepts a sequence clipboard non-const reference parameter.

12.64.3.24 seq_cut()

```
void seq64::seqmenu::seq_cut ( ) [private]
```

Todo A lot of seq_cut() can be offloaded to a (new) perform member function that takes a sequence clipboard non-const reference parameter.

```
12.64.3.25 seq_paste()
```

```
void seq64::seqmenu::seq_paste ( ) [private]
```

Then it sets the dirty flag for the destination sequence.

Todo All of seq_paste() can be offloaded to a (new) perform member function with a const clipboard reference parameter.

12.64.3.26 seq_clear_perf()

```
void seq64::seqmenu::seq_clear_perf ( ) [private]
```

12.64.3.27 set_bus_and_midi_channel()

Parameters

	bus	The MIDI buss number to set (bus vs buss? You decide.)
ſ	ch	The MIDI channel number to set.

12.64.3.28 set_transposable()

Parameters

flag	The value to use to set the flag.
------	-----------------------------------

12.64.3.29 mute_all_tracks()

```
void seq64::seqmenu::mute_all_tracks ( ) [inline], [private]
```

12.64.3.30 unmute_all_tracks()

```
void seq64::seqmenu::unmute_all_tracks ( ) [inline], [private]
```

12.64.3.31 toggle_all_tracks()

```
void seq64::seqmenu::toggle_all_tracks ( ) [inline], [private]
```

```
12.64.3.32 on_realize()
void seq64::seqmenu::on_realize ( ) [private]
12.64.4 Friends And Related Function Documentation
12.64.4.1 mainwnd
friend class mainwnd [friend]
12.64.5 Field Documentation
12.64.5.1 m_menu
Gtk::Menu* seq64::seqmenu::m_menu [private]
12.64.5.2 m_mainperf
perform& seq64::seqmenu::m_mainperf [private]
12.64.5.3 m_clipboard
sequence seq64::seqmenu::m_clipboard [private]
12.64.5.4 m_seqedit
seqedit* seq64::seqmenu::m_seqedit [private]
Change Note Added by Chris on 2015-08-02 based on compiler warnings and a comment warning in the seq_edit()
function. We'll save the result of that function here, and will let valgrind tell us later if Gtkmm takes care of it.
12.64.5.5 m_eventedit
eventedit* seq64::seqmenu::m_eventedit [private]
12.64.5.6 m_current_seq
int seq64::seqmenu::m_current_seq [private]
12.64.5.7 m_modified
```

Todo We need to make sure that the perform object is in control of the modification flag.

bool seq64::seqmenu::m_modified [private]

12.65 seq64::seqroll Class Reference

Implements the piano roll section of the pattern editor.

Inheritance diagram for seq64::seqroll:



Public Member Functions

• seqroll (perform &perf, sequence &seq, int zoom, int snap, seqkeys &seqkeys_wid, int pos, Gtk::Adjustment &hadjust, Gtk::Adjustment &vadjust, int ppqn=SEQ64_USE_DEFAULT_PPQN)

Principal constructor.

virtual ∼seqroll ()

Provides a destructor to delete allocated objects.

void set_snap (int snap)

Sets the snap to the given value, and then resets the view.

void set_zoom (int zoom)

Sets the zoom to the given value, and then resets the view.

• void set_note_length (int note_length)

'Setter' function for member m note length

• int note_off_length () const

'Getter' function for member m_note_length, adjusted for the note_off_margin.

bool add_note (midipulse tick, int note, bool paint=true)

Convenience wrapper for sequence::add_note().

· void add_chord (midipulse tick, int note)

Convenience wrapper for sequence::add_chord().

void set_key (int key)

Sets the music key to the given value, and then resets the view.

void set_scale (int scale)

Sets the music scale to the given value, and then resets the view.

void set chord (int chord)

Sets the current chord to the given value.

void set_data_type (midibyte status, midibyte control)

Sets the status to the given parameter, and the CC value to the given optional control parameter, which defaults to 0.

void set background sequence (bool state, int seq)

This function sets the given sequence onto the piano roll of the pattern editor, so that the musician can have another pattern to play against.

void update_pixmap ()

This function draws the background pixmap on the main pixmap, and then draws the events on it.

• void update_sizes ()

Update the sizes of items based on zoom, PPQN, BPM, BW (beat width) and more.

void update_background ()

Updates the background of this window.

void draw_background_on_pixmap ()

Draws the main pixmap.

void draw_events_on_pixmap ()

Fills the main pixmap with events.

void draw selection on window ()

Draws the current selecton on the main window.

void draw_progress_on_window ()

Draw a progress line on the window.

void reset ()

This function basically resets the whole widget as if it were realized again.

void update_and_draw (int force=false)

Wraps up some common code.

· void redraw ()

Redraws unless m_ignore_redraw is true.

void redraw_events ()

Redraws events unless m_ignore_redraw is true.

· void start_paste ()

Starts a paste operation.

- void complete_paste ()
- void complete_paste (int x, int y)

Completes a paste operation.

• void follow_progress ()

Private Member Functions

virtual void force_draw ()

Set the pixmap into the window and then draws the selection on it.

void horizontal adjust (double step)

This function provides optimization for the on_scroll_event() function.

void vertical_adjust (double step)

This function provides optimization for the on_scroll_event() function.

void snap_y (int &y)

Snaps the y value to the piano-key "height".

void snap_x (int &x)

Performs a 'snap' operation on the x coordinate.

- void convert_xy (int x, int y, midipulse &ticks, int ¬e)
- void convert tn (midipulse ticks, int note, int &x, int &y)

This function takes the given note and tick, and returns the screen coordinates via the pointer parameters.

void xy_to_rect (int x1, int y1, int x2, int y2, int &x, int &y, int &w, int &h)

Converts rectangle corner coordinates to a starting coordinate, plus a width and height.

void convert_tn_box_to_rect (midipulse tick_s, midipulse tick_f, int note_h, int note_l, int &x, int &y, int &w, int &h)

Converts a tick/note box to an x/y rectangle.

void convert_sel_box_to_rect (midipulse tick_s, midipulse tick_f, int note_h, int note_l)

A convenience function wrapping a common call to convert_tn_box_to_rect().

void get selected box (midipulse &tick s, int ¬e h, midipulse &tick f, int ¬e l)

A convenience function wrapping a common call to m_seq.get_selected_box() and convert_tn_box_to_rect().

void draw_events_on (Glib::RefPtr< Gdk::Drawable > draw)

Draws events on the given drawable area.

• int idle redraw ()

Draw the events on the main window and on the pixmap.

- int idle_progress ()
- void change_horz ()

Change the horizontal scrolling offset and redraw.

· void change_vert ()

Change the vertical scrolling offset and redraw.

• void move_selection_box (int dx, int dy)

Function to allow motion of the selection box via the arrow keys.

void move_selected_notes (int dx, int dy)

Proposed new function to encapsulate the movement of selections even more fully.

void grow_selected_notes (int dx)

Proposed new function to encapsulate the movement of selections even more fully.

void set_adding (bool adding)

Changes the mouse cursor pixmap according to whether a note is being added or not.

void update_mouse_pointer (bool adding=false)

Updates the mouse pointer, implementing a context-sensitive mouse.

- bool button_press_initial (GdkEventButton *ev, int &norm_x, int &snapped_x, int &snapped_y)
- void align selection (midipulse &tick s, int ¬e h, midipulse &tick f, int ¬e l, int snapped x)

Get the box that selected elements are in.

• bool button_press (GdkEventButton *ev)

Implements the on-button-press event handling for the Seq24 style of mouse interaction.

bool button_release (GdkEventButton *ev)

Implements the on-button-release event handling for the Seq24 style of mouse interaction.

• bool motion_notify (GdkEventMotion *ev)

Seq24-style on-motion mouse interaction.

void clear_selected ()

'Setter' function for member m_old

· void clear old ()

'Setter' function for member m_old

· void clear flags ()

Clears all the mouse-action flags.

int scroll offset x (int x) const

Useful x calculation.

int scroll_offset_y (int y) const

Useful y calculation.

void set_current_offset_x_y (int x, int y)

Useful x calculation.

• bool adding () const

'Getter' function for member m_adding

• bool selecting () const

'Getter' function for member m_selecting

· bool growing () const

'Getter' function for member m_growing

· bool normal action () const

Indicates if we're drag-pasting, selecting, moving, growing, or pasting.

· bool select_action () const

Indicates if we're selecting, moving, growing, or pasting.

bool drop_action () const

Indicates if we're moving or pasting.

• bool moving () const

'Getter' function for member m_moving

void on_realize ()

Implements the on-realize event handling.

bool on expose event (GdkEventExpose *ev)

Implements the on-expose event handling.

bool on_button_press_event (GdkEventButton *ev)

Implements the on-button-press event handling.

• bool on_button_release_event (GdkEventButton *ev)

Implements the on-button-release event handling.

bool on_motion_notify_event (GdkEventMotion *ev)

Implements the on-motion-notify event handling.

bool on_focus_in_event (GdkEventFocus *)

Implements the on-focus event handling.

bool on_focus_out_event (GdkEventFocus *)

Implements the on-unfocus event handling.

bool on_key_press_event (GdkEventKey *ev)

Implements the on-key-press event handling.

bool on_scroll_event (GdkEventScroll *a_ev)

Implements the on-scroll event handling.void on_size_allocate (Gtk::Allocation &)

Implements the on-size-allocate event handling.

• bool on_leave_notify_event (GdkEventCrossing *p0)

Implements the on-leave-notify event handling.

• bool on_enter_notify_event (GdkEventCrossing *p0)

Implements the on-enter-notify event handling.

Private Attributes

Gtk::Adjustment & m_horizontal_adjust

For accessing on_key_press_event().

Gtk::Adjustment & m_vertical_adjust

We need direct access to the vertical scrollbar if we want to be able to make it follow PageUp and PageDown.

· rect m old

The previous selection rectangle, used for undrawing it.

· rect m selected

Used in moving and pasting notes.

• sequence & m_seq

Provides a reference to the sequence represented by piano roll.

seqkeys & m_seqkeys_wid

Holds a reference to the seqkeys pane that is associated with the seqroll piano roll.

• FruitySeqRollInput m_fruity_interaction

Provides a fruity input object, whether it is needed or not.

int m_pos

A position value.

• int m zoom

Zoom setting, means that one pixel == m_zoom ticks.

int m_snap

The grid-snap setting for the piano roll grid.

• int m ppqn

The value of PPQN for the current MIDI song.

• int m_note_length

Holds the note length in force for this sequence.

• int m scale

Indicates the musical scale in force for this sequence.

• int m_chord

Indicates the current chord in force for this sequence for inserting notes.

· int m key

Indicates the musical key in force for this sequence.

bool m_adding

Set when in note-adding mode.

· bool m selecting

Set when highlighting a bunch of events.

bool m_moving

Set when moving a bunch of events.

bool m_moving_init

Indicates the beginning of moving some events.

• bool m_growing

Indicates that the notes are to be extended or reduced in length.

bool m_painting

Indicates the painting of events.

bool m paste

Indicates that we are in the process of painting notes.

bool m_is_drag_pasting

Indicates the drag-pasting of events.

· bool m is drag pasting start

Indicates the drag-pasting of events.

bool m_justselected_one

Indicates the selection of one event.

int m_move_delta_x

Tells where the dragging started, the x value.

· int m_move_delta_y

Tells where the dragging started, the y value.

int m_move_snap_offset_x

This item is used in the fruityseqroll module.

· int m_progress_x

Provides the location of the progress bar.

· int m_scroll_offset_ticks

The horizontal value of the scroll window in units of ticks/pulses/divisions.

• int m_scroll_offset_key

The vertical offset of the scroll window in units of MIDI notes/keys.

int m scroll offset x

The horizontal value of the scroll window in units of pixels.

int m_scroll_offset_y

The vertical value of the scroll window in units of pixels.

· bool m transport follow

TBD.

bool m_trans_button_press

TBD.

· int m background sequence

Holds the value of the musical background sequence that is shown in cyan (formerly grey) on the background of the piano roll.

bool m_drawing_background_seq

Set to true if the drawing of the background sequence is to be done.

· midibyte m_status

Set to true to avoid the call to update_and_draw().

• midibyte m_cc

The current MIDI control value selected in the sequdit.

Friends

· class FruitySeqRollInput

This friend implements fruity interaction-specific behavior.

Additional Inherited Members

12.65.1 Constructor & Destructor Documentation

12.65.1.1 segroll()

```
seq64::seqroll::seqroll (
    perform & p,
    sequence & seq,
    int zoom,
    int snap,
    seqkeys & seqkeys_wid,
    int pos,
    Gtk::Adjustment & hadjust,
    Gtk::Adjustment & vadjust,
    int ppqn = SEQ64_USE_DEFAULT_PPQN )
```

Parameters

p	The performance object that helps control this piano roll. Note that we can get the perform object from the sequence, and save a parameter. Low priority change.
seq	The sequence object represented by this piano roll.
zoom	The initial zoom of this piano roll.
snap	The initial grid snap of this piano roll.
seqkeys_wid	A reference to the piano keys window that is shown to the left of this piano roll.
pos	A position parameter. See the description of seqroll::m_pos . This is actually the sequence number, and is currently unused. However, we're sure we can find a use for it sometime.
hadjust	Represents the horizontal scrollbar of this window. It is actually created by the "parent" sequential object.
vadjust	Represents the vertical scrollbar of this window. It is actually created by the "parent" seqedit object.
ppqn	The initial value of the PPQN for this sequence. Useful in scale calculations.

12.65.1.2 ∼seqroll()

```
seq64::seqroll::\sim seqroll ( ) [virtual]
```

The only thing to delete here is the clipboard. Except it is never used, so is commented out.

12.65.2 Member Function Documentation

12.65.2.1 set_snap()

Parameters

snap Provides the sname value to set.

12.65.2.2 set_zoom()

Parameters

zoom The desired zoom value, assumed to be validated already. See the seqedit::set_zoom() function.

12.65.2.3 set_note_length()

```
void seq64::seqroll::set\_note\_length (
```

bool paint = true)

The length parameters is obtained from the note_off_length() function. This sets the note length at a little less than the snap value.

Parameters

tick	The time destination of the new note, in pulses.
note	The pitch destination of the new note.
paint	If true, repaint to be left with just the inserted event. The default is true. The value of false is useful in inserting a number of events and saving the repainting until last. It is a bit tricky, as the default paint value for sequence::add_note() is false.

12.65.2.6 add_chord()

Implicit parameters are the m_chord and note_off_length() members. The latter deducts just a little from the snap value.

Parameters

tick	The tick at which to add the chord.
note	The base (bottom) note of the chord.

12.65.2.7 set_key()

Parameters

12.65.2.8 set_scale()

Parameters

scale	The desired scale value.

12.65.2.9 set_chord()

Parameters

12.65.2.10 set_data_type()

Unlike the same function in seqevent, this version does not redraw. Used by seqedit.

12.65.2.11 set_background_sequence()

```
void seq64::seqroll::set_background_sequence ( bool \ state, int \ seq )
```

The state parameter sets the boolean m_drawing_background_seq.

Parameters

state	If true, the background sequence will be drawn.
seq	Provides the sequence number, which is checked against the SEQ64_IS_LEGAL_SEQUENCE() macro before being used. This macro allows the value SEQ64_SEQUENCE_LIMIT, which disables the
	background sequence.

12.65.2.12 update_pixmap()

```
void seq64::seqroll::update_pixmap ( )
```

12.65.2.13 update_sizes()

```
void seq64::seqroll::update_sizes ( )
```

It brings the scrollbar back to the beginning, resets the upper limit to the number of ticks in the sequence, sets the page-size based on the window size and the zoom factor.

The horizontal step increment is 1 semiquaver (1/16) note per zoom level. The horizontal page increment is currently always one bar. We may want to make that larger for scrolling after the progress bar.

Tha maximum value set for the scrollbar brings it to the last "page" of the piano roll.

The vertical size are also adjusted. More on the story later.

```
12.65.2.14 update_background()
```

```
void seq64::seqroll::update_background ( )
```

The first thing done is to clear the background, painting it white.

12.65.2.15 draw_background_on_pixmap()

```
void seq64::seqroll::draw_background_on_pixmap ( )
```

12.65.2.16 draw_events_on_pixmap()

```
void seq64::seqroll::draw_events_on_pixmap ( )
```

Just calls draw_events_on().

12.65.2.17 draw_selection_on_window()

```
void seq64::seqroll::draw_selection_on_window ( )
```

Note the parameters of draw drawable(), which we need to be sure of to draw thicker boxes.

```
    x and y position of rectangle to draw
    x and y position in drawable where rectangle should be drawn
    width and height of rectangle to draw
```

A final parameter of false draws an unfilled rectangle. Orange makes it a little more clear that we're pasting, I think. We also want to try to thicken the lines somehow.

```
12.65.2.18 draw_progress_on_window()
```

```
void seq64::seqroll::draw_progress_on_window ( )
```

This is done by first blanking out the line with the background, which contains white space and grey lines, using the the draw_drawable function. Remember that we wrap the draw_drawable() function so it's parameters are xsrc, ysrc, xdest, ydest, width, and height.

Note that the progress-bar position is based on the sequence::get_last_tick() value, the current zoom, and the current scroll-offset x value.

Finally, we had an issue with the selection box flickering, which seems to be solved satisfactorily by not drawing it if a select action is in force. Hopefully no one needs to select notes on the fly and see the progress bar moving at the same time! Another tactic is to draw progress only when the performance is running. This has the benefit/drawback that the progress bar is left where it stops. Consider an enumeration of options: normal, when-not-selecting, and when-running.

12.65.2.19 reset()

```
void seq64::seqroll::reset ( )
```

It's almost identical to the change_horz() function, just calling update_sizes() before update_and_draw().

12.65.2.20 update_and_draw()

Parameters

force If true, force an immediate draw, otherwise just queue up a draw. This value defaults to false.

12.65.2.21 redraw()

```
void seq64::seqroll::redraw ( )
```

Somewhat similar to seqevent::redraw(). Actually, we don't seem to need to ignore redraw when making settings in the seqedit constructor, so this member no longer exists.

12.65.2.22 redraw_events()

```
void seq64::seqroll::redraw_events ( )
```

Actually, that member is not needed and no longer exists.

12.65.2.23 start_paste()

```
void seq64::seqroll::start_paste ( )
```

A duplicate of the one in seqedit.

Parameters

step

Provides the step value to use for adjusting the horizontal scrollbar. See gui_drawingarea_gtk2::scroll_hadjust() for more information.

12.65.2.29 vertical_adjust()

A duplicate of the one in seqedit.

Parameters

step

Provides the step value to use for adjusting the vertical scrollbar. See gui_drawingarea_gtk2::scroll_vadjust() for more information.

12.65.2.30 snap_y()

Parameters

	out	у	The y-value to be snapped.
--	-----	---	----------------------------

12.65.2.31 snap_x()

This function is similar to snap_y(), but it calculates a modulo value from the snap and zoom settings.

```
- m_snap = number pulses to snap to
- m_zoom = number of pulses per pixel
```

Therefore, m_snap / m_zoom = number pixels to snap to.

Parameters

out	Х	Provides the x-value to be snapped and returned. A return value would be better.
-----	---	--

12.65.2.32 convert_xy()

12.65.2.33 convert_tn()

This function is the "inverse" of convert_xy().

Parameters

	tick	Provides the horizontal value in MIDI pulses.
	note	Provides the vertical value, a note value.
out	Х	Provides the destination x value of the coordinate.
out	У	Provides the destination y value of the coordinate.

12.65.2.34 xy_to_rect()

This function checks the mins / maxes, and then fills in the x, y, width, and height values.

We should refactor this function to use the utility class seqroll::rect as the destination for the conversion.

Parameters

	x1	The x value of the first corner.
	y1	The y value of the first corner.
	x2	The x value of the second corner.
	y2	The y value of the second corner.
out	Х	The destination for the x value in pixels.
out	У	The destination for the y value in pixels.
out	W	The destination for the rectangle width in pixels.
out	h	The destination for the rectangle height value in pixels.

12.65.2.35 convert_tn_box_to_rect()

We should refactor this function to use the utility class seqroll::rect as the destination for the conversion.

Parameters

	tick_s	The starting tick of the rectangle.
	tick_f	The finishing tick of the rectangle.
	note⊷ h	The high note of the rectangle.
	_''	
	note⊷	The low note of the rectangle.
	_/	
out	X	The destination for the x value in pixels.
out	У	The destination for the y value in pixels.
out	W	The destination for the rectangle width in pixels.
out	h	The destination for the rectangle height value in pixels.

12.65.2.36 convert_sel_box_to_rect()

Parameters

tick_s	The starting tick of the rectangle.
tick_f	The finishing tick of the rectangle.
note↔ _h	The high note of the rectangle.
note⇔ I	The low note of the rectangle.

12.65.2.37 get_selected_box()

```
void seq64::seqroll::get_selected_box (
    midipulse & tick_s,
    int & note_h,
    midipulse & tick_f,
    int & note_l ) [private]
```

Parameters

out	tick_s	The starting tick of the rectangle.
out	tick_f	The finishing tick of the rectangle.
out	note⊷	The high note of the rectangle.
	_h	
out	note⊷	The low note of the rectangle.
	_/	

12.65.2.38 draw_events_on()

"Method 0" draws the background sequence, if active. "Method 1" draws the sequence itself.

Parameters

```
draw The "drawable" area to draw on.
```

12.65.2.39 idle_redraw()

```
int seq64::seqroll::idle_redraw ( ) [private]
```

12.65.2.40 idle_progress()

```
int seq64::seqroll::idle_progress ( ) [private]

12.65.2.41 change_horz()

void seq64::seqroll::change_horz ( ) [private]

Roughly similar to seqevent::change_horz().

12.65.2.42 change_vert()

void seq64::seqroll::change_vert ( ) [private]
```

```
12.65.2.43 move_selection_box()
```

We now let the Enter key to finish pasting and deselect the moved notes. With the mouse, selecting all notes, copying them, and moving the selection box, pasting can be completed with either a left-click or the Enter key.

We have a weird problem on our main system where the selection box is very flickery. But it works fine on another system. A Gtk-2 issue? Now it seems to work fine, after an update. No, it seems to work well in sequences that have non-note events amongst the note events.

Parameters

```
    dx The amount to move the selection box. Values are -1, 0, or 1. -1 is left one snap, 0 is no movement horizontally, and 1 is right one snap.
    dy The amount to move the selection box. Values are -1, 0, or 1. -1 is up one snap, 0 is no movement vertically, and 1 is down one snap.
```

12.65.2.44 move_selected_notes()

Works with the four arrow keys.

Note that the movement vertically is different for the selection box versus the notes. While the movement values are -1, 0, or 1, the differences are as follows:

```
    Selection box vertical movement:
    -1 is up one note snap.
    0 is no vertical movement.
    +1 is down one note snap.
```

- Note vertical movement:

 - 1 is down one note.
 0 is no note vertical movement.
 +1 is up one note.

Parameters

- dx The amount to move the selection box or the selection horizontally. Values are -1 (left one time snap), 0 (no movement), and +1 (right one snap). Obviously values other than +-1 can be used for larger movement, but the GUI doesn't yet support that ... we could implement movement by "pages" some day.
- dy The amount to move the selection box or the selection vertically. See the notes above.

12.65.2.45 grow_selected_notes()

Parameters

dx

The amount to grow the selection horizontally. Values are -1 (left one time snap), 0 (no stretching), and +1 (right one snap). Obviously values other than +-1 can be used for larger stretching, but the GUI doesn't yet support that.

12.65.2.46 set_adding()

What calls this? It is actually a right click. Not present in the "fruity" implementation. Now moved to the normal seqroll class.

Parameters

```
adding True if adding a note.
```

12.65.2.47 update_mouse_pointer()

Moved here from the "fruity" seqroll class.

12.65.2.48 button_press_initial()

12.65.2.49 align_selection()

```
void seq64::seqroll::align_selection (
    midipulse & tick_s,
    int & note_h,
    midipulse & tick_f,
    int & note_l,
    int snapped_x ) [private]
```

Save offset that we get from the snap above. Align selection for drawing. Could be used in XRollInput::on_button
_press_event().

12.65.2.50 button_press()

This function now uses the needs update flag to determine if the perform object should modify().

Parameters

ev Provides the button-press event to process.

Returns

Returns the value of needs_update. It used to return only true.

12.65.2.51 button_release()

This function now uses the needs_update flag to determine if the perform object should modify().

Parameters

ev Provides the button-release event to process.

Returns

Returns the value of needs_update. It used to return only true.

If in moving mode, adjust for snap and convert deltas into screen coordinates. Since delta_note was from delta_y, it will be flipped (delta_y[0] = note[127], etc.), so we have to adjust.

A left/middle click converts deltas into screen coordinates, then pushs the undo state. Shift causes a "stretch selected" which currently acts like a "move selected" operation. BUG? Otherwise, Ctrl indirectly allows a "grow selected" operation.

Minor new feature. If the Super (Mod4, Windows) key is pressed when release, keep the adding state in force. One can then use the unadorned left-click key to add notes. Right click to reset the adding mode. This feature is enabled only if allowed by the settings (but is true by default). See the same code in perfrollinput.cpp.

12.65.2.52 motion_notify()

We could allow move painting for chords, but that would take some tricky code to move all of the notes of the chord. And allowing painting here currently affects only one note after the chord itself is created.

Parameters

ev Provides the button-release event to process.

Returns

Returns true if the event was processed.

```
12.65.2.53 clear_selected()
```

```
void seq64::seqroll::clear_selected ( ) [inline], [private]
```

12.65.2.54 clear_old()

```
void seq64::seqroll::clear_old ( ) [inline], [private]
```

12.65.2.55 clear_flags()

```
void seq64::seqroll::clear_flags ( ) [inline], [private]
```

12.65.2.56 scroll_offset_x()

Offsets the x value by the x origin of the current page.

Parameters

```
x The x value to offset.
```

12.65.2.57 scroll_offset_y()

Offsets the y value by the y origin of the current page.

Parameters

```
y The y value to offset.
```

12.65.2.58 set_current_offset_x_y()

Offsets the current x value by the x origin of the current page.

Parameters

```
x The x value to offset.
```

void set_current_offset_x (int x) { $m_current_x = x + m_scroll_offset_x$; } Useful y calculation. Offsets the current y value by the y origin of the current page.

Parameters

```
y The y value to offset.
```

void set_current_offset_y (int y) { $m_current_y = y + m_scroll_offset_y$; } Useful x and y calculation. Offsets the current x and y values by the x and y origin of the current page.

Parameters

X	The y value to offset.
у	The y value to offset.

12.65.2.59 adding()

```
bool seq64::seqroll::adding ( ) const [inline], [private]
```

12.65.2.60 selecting()

```
bool seq64::seqroll::selecting ( ) const [inline], [private]
```

12.65.2.61 growing()

```
bool seq64::seqroll::growing ( ) const [inline], [private]
```

12.65.2.62 normal_action()

```
bool seq64::seqroll::normal_action ( ) const [inline], [private]
```

Returns

Returns true if one of those five flags are set.

12.65.2.63 select_action()

```
bool seq64::seqroll::select_action ( ) const [inline], [private]
```

Returns

Returns true if one of those four flags are set.

12.65.2.64 drop_action()

```
bool seq64::seqroll::drop_action ( ) const [inline], [private]
```

Returns

Returns true if one of those two flags are set.

12.65.2.65 moving()

```
bool seq64::seqroll::moving ( ) const [inline], [private]
```

12.65.2.66 on_realize()

```
void seq64::seqroll::on_realize ( ) [private]
```

12.65.2.67 on_expose_event()

Parameters

```
ev The expose event to process.
```

Returns

Always returns true.

12.65.2.68 on_button_press_event()

Parameters

ev The expose event to process.

Returns

Returns the result of the Seq24 interaction or the Fruity interaction, that is, the return value of Seq24Seq← RollInput::on_button_press_event() or FruitySeqRollInput::on_button_press_event().

12.65.2.69 on_button_release_event()

This function checks the "rc" interaction-method option, and calls the forwarding function for the seq24 or the fruity interaction method. Might be a good case to prefer inheritance and not try to support changing the interaction method without a restart of Sequencer64.

Parameters

ev The button release event to process.

Returns

Returns the return value of Seq24SeqRollInput::on_button_release_event() or FruitySeqRollInput::on_ \leftarrow button_release_event().

12.65.2.70 on_motion_notify_event()

Parameters

ev The motion-notification event to process.

Returns

Returns the return value of Seq24SeqRollInput::on_motion_notify_event() or FruitySeqRollInput::on_motion \leftarrow _notify_event().

12.65.2.71 on_focus_in_event()

Sets the GDK HAS_FOCUS flag. Parameter "ev" is the event-focus event, not used.

Returns

Always returns false.

12.65.2.72 on_focus_out_event()

Resets the GDK HAS_FOCUS flag. Parameter "ev" is the event-focus event, not used.

Returns

Always returns false.

12.65.2.73 on_key_press_event()

The start/end key may be the same key (i.e. SPACEBAR). Allow toggling when the same key is mapped to both triggers (i.e. SPACEBAR).

Concerning the usage of the arrow keys in this function: This code is reached, but has no visible effect. Why? I think they were meant to move the point for playback. We may have a bug with our new handling of triggers (unlikely), or maybe these depend upon the proper playback mode. In any case, the old functionality is preserved. However, if there are notes selected, then these keys support selection movement.

Since the Up and Down arrow keys are used for movement, we'd have to check selection status before trying to use them to move up and down in the piano roll, in smaller steps than the new Page-Up and Page-Down key support.

Parameters

```
ev The key-press event to process.
```

Returns

Returns true if the key-press was handled.

I think we should be able to move and remove notes while playing, which is already supported using the mouse.

if (! perf().is_playing)

12.65.2.74 on_scroll_event()

This scroll event only handles basic scrolling without any modifier keys such as the Ctrl or Shift masks. The seqedit class handles that fun stuff.

Note that this function seems to duplicate the functionality of seqkeys::on_scroll_event(). Do we really need both?
Which one do we need?

Parameters

```
ev The scroll event to process.
```

Returns

Returns true if the scroll event was handled.

12.65.2.75 on_size_allocate()

Calls the base-class version of this function and sets m_window_x and m_window_y to the width and height of the allocation parameter. Then calls update_sizes().

Parameters

a The GDK allocation event object.

12.65.2.76 on_leave_notify_event()

Calls m_seqkeys_wid.set_hint_state(false). Parameter "ev" is the event-crossing event, not used.

Returns

Always returns false.

12.65.2.77 on_enter_notify_event()

Calls m_seqkeys_wid.set_hint_state(true). Parameter "ev" is the event-crossing event, not used.

Returns

Always returns false.

12.65.3 Friends And Related Function Documentation

12.65.3.1 FruitySeqRollInput

```
friend class FruitySeqRollInput [friend]
```

We've absorbed the Seq24SeqRollInput class functionality back into seqroll, to save code.

12.65.4 Field Documentation

12.65.4.1 m_horizontal_adjust

```
Gtk::Adjustment& seq64::seqroll::m_horizontal_adjust [private]
```

It would be good to be able to avoid this access!

Change Note layk 2016-10-17 Issue #46. No need for this declaration now, due to the fix in seqedit.

friend class sequedit; We need direct access to the horizontal scrollbar if we want to be able to make it follow the progress bar.

```
12.65.4.2 m_vertical_adjust

Gtk::Adjustment& seq64::seqroll::m_vertical_adjust [private]

12.65.4.3 m_old

rect seq64::seqroll::m_old [private]

12.65.4.4 m_selected

rect seq64::seqroll::m_selected [private]

12.65.4.5 m_seq

sequence& seq64::seqroll::m_seq [private]

12.65.4.6 m_seqkeys_wid

seqkeys& seq64::seqroll::m_seqkeys_wid [private]
```

12.65.4.7 m_fruity_interaction

FruitySeqRollInput seq64::seqroll::m_fruity_interaction [private]

```
12.65.4.8 m_pos
int seq64::seqroll::m_pos [private]
Need to clarify what exactly this member is used for.
12.65.4.9 m_zoom
int seq64::seqroll::m_zoom [private]
12.65.4.10 m_snap
int seq64::seqroll::m_snap [private]
Same meaning as for the event-bar grid. This value is the denominator of the note size used for the snap.
12.65.4.11 m_ppqn
int seq64::seqroll::m_ppqn [private]
Supports values other than the default of 192.
12.65.4.12 m_note_length
int seq64::seqroll::m_note_length [private]
Used in the seq24seqroll module only.
12.65.4.13 m_scale
int seq64::seqroll::m_scale [private]
12.65.4.14 m_chord
int seq64::seqroll::m_chord [private]
12.65.4.15 m_key
int seq64::seqroll::m_key [private]
12.65.4.16 m_adding
```

This flag was moved from both the fruity and the seq24 seqroll classes.

bool seq64::seqroll::m_adding [private]

```
12.65.4.17 m_selecting
bool seq64::seqroll::m_selecting [private]
12.65.4.18 m_moving
bool seq64::seqroll::m_moving [private]
12.65.4.19 m_moving_init
bool seq64::seqroll::m_moving_init [private]
Used in the fruity and seq24 mouse-handling modules.
12.65.4.20 m_growing
bool seq64::seqroll::m_growing [private]
12.65.4.21 m_painting
bool seq64::seqroll::m_painting [private]
Used in the fruity and seq24 mouse-handling modules.
12.65.4.22 m_paste
bool seq64::seqroll::m_paste [private]
12.65.4.23 m_is_drag_pasting
bool seq64::seqroll::m_is_drag_pasting [private]
Used in the fruity mouse-handling module.
12.65.4.24 m_is_drag_pasting_start
bool seq64::seqroll::m_is_drag_pasting_start [private]
Used in the fruity mouse-handling module.
12.65.4.25 m_justselected_one
bool seq64::seqroll::m_justselected_one [private]
```

Used in the fruity mouse-handling module.

```
12.65.4.26 m_move_delta_x
int seq64::seqroll::m_move_delta_x [private]
12.65.4.27 m_move_delta_y
int seq64::seqroll::m_move_delta_y [private]
12.65.4.28 m_move_snap_offset_x
int seq64::seqroll::m_move_snap_offset_x [private]
12.65.4.29 m_progress_x
int seq64::seqroll::m_progress_x [private]
12.65.4.30 m scroll offset ticks
int seq64::seqroll::m_scroll_offset_ticks [private]
12.65.4.31 m_scroll_offset_key
int seq64::seqroll::m_scroll_offset_key [private]
12.65.4.32 m_scroll_offset_x
int seq64::seqroll::m_scroll_offset_x [private]
12.65.4.33 m_scroll_offset_y
int seq64::seqroll::m_scroll_offset_y [private]
12.65.4.34 m_transport_follow
bool seq64::seqroll::m_transport_follow [private]
12.65.4.35 m_trans_button_press
bool seq64::seqroll::m_trans_button_press [private]
```

12.65.4.36 m_background_sequence

```
int seq64::seqroll::m_background_sequence [private]
```

12.65.4.37 m_drawing_background_seq

```
bool seq64::seqroll::m_drawing_background_seq [private]
```

12.65.4.38 m status

```
midibyte seq64::seqroll::m_status [private]
```

Used in set_background_sequence(), change_horz(), change_vert(), reset().... Never set to true, except in seq24, let's just comment it out for now. It hasn't been used in sequencer64 for awhile now.

bool m_ignore_redraw; The current status/event selected in the seqedit. Not used in seqroll at present.

12.65.4.39 m_cc

```
midibyte seq64::seqroll::m_cc [private]
```

Not used in seqroll at present.

12.66 seq64::seqtime Class Reference

This class implements the piano time, whatever that is.

Inheritance diagram for seq64::seqtime:



Public Member Functions

• seqtime (sequence &seq, perform &p, int zoom, Gtk::Adjustment &hadjust, int ppqn=SEQ64_USE_DEFA ∪ ULT_PPQN)

Principal constructor.

virtual ∼seqtime ()

Let's provide a do-nothing virtual destructor.

```
· void reset ()
```

Sets the scroll offset tick and x values, updates the sizes and the pixmap, and resets the window.

· void redraw ()

Very similar to the reset() function, except it doesn't update the sizes.

void set_zoom (int zoom)

Sets the zoom to the given value and resets the window.

Private Member Functions

```
void draw_pixmap_on_window ()
```

Draws the pixmap on the window.

- void draw_progress_on_window ()
- void update_pixmap ()

Updates the pixmap.

void change_horz ()

Changes the scrolling horizontal offset, updates the pixmap, and forces a redraw.

• void update_sizes ()

Updates the pixmap to a new size and queues up a draw operation.

• bool idle_progress ()

Simply returns true.

void on_realize ()

Called when the window is drawn.

• bool on expose event (GdkEventExpose *a ev)

Implements the on-expose event handler.

void on_size_allocate (Gtk::Allocation &)

Implements the on-size-allocate event handler.

bool on_button_press_event (GdkEventButton *)

Implements the on-button-press event handler.

bool on_button_release_event (GdkEventButton *)

Implements the on-button-release event handler.

Private Attributes

```
    sequence & m seq
```

- int m_scroll_offset_ticks
- int m_scroll_offset_x
- int m_zoom

one pixel == m_zoom ticks

• int m_ppqn

Additional Inherited Members

12.66.1 Constructor & Destructor Documentation

12.66.1.1 segtime()

In the constructor you can only allocate colors; get_window() returns 0 because the window is not yet realized>

```
12.66.2.4 draw_pixmap_on_window()

void seq64::seqtime::draw_pixmap_on_window ( ) [private]

12.66.2.5 draw_progress_on_window()

void seq64::seqtime::draw_progress_on_window ( ) [private]

12.66.2.6 update_pixmap()

void seq64::seqtime::update_pixmap ( ) [private]
```

When the zoom is at 32 ticks per pixel, there is a thick bar for every measure, and a measure number and major time division every 4 measures.at the default PPQN of 192.

A major line is a line that has a measure number in the timeline. The number of measures in a major line is 1 for zooms from 1:1 to 1:8; 2 for zoom 1:16; 4 for zoom 1:32; 8 for zoom 1:64 (new); and 16 for zoom 1:128. Zooms 1:64 and above look good only for high PPQN values.

We calculate the measure length in 32nd notes. This value is, of course, 32, when the time signature is 4/4. Then calculate measures/line. "measures_per_major" is more like "measures per major line". With a higher zoom than 32, this calculation yields a floating-point exception if m_zoom

32, so we rearrange the calculation and hope that it still works out the

same for smaller values.

Stazed:

At 32, a bar every measure.

zoom ml	32	16	8	4	1
1	128				
2	64				
4	32	16	8		
8	16m	8	4	2	1
16	8m	4	2	1	1
32	4m	2	1	1	1
64	2m	1	1	1	1
128	1m	1	1	1	1

Todo Sizing needs to be controlled by font parameters. Instead of 19 or 20, estimate the width of 3 letters. Instead of 9 pixels down, use the height of the seqtime and the height of a character.

```
12.66.2.7 change_horz()

void seq64::seqtime::change_horz ( ) [private]

12.66.2.8 update_sizes()

void seq64::seqtime::update_sizes ( ) [private]

12.66.2.9 idle_progress()

bool seq64::seqtime::idle_progress ( ) [inline], [private]

12.66.2.10 on_realize()

void seq64::seqtime::on_realize ( ) [private]
```

Call the base-class version of this function first. Then addition resources are allocated.

```
12.66.2.11 on_expose_event()
```

Gtk::Allocation & a) [private]

```
12.66.2.13 on_button_press_event()
bool seq64::seqtime::on_button_press_event (
             GdkEventButton * ) [inline], [private]
Simply returns false.
12.66.2.14 on_button_release_event()
bool seq64::seqtime::on_button_release_event (
             GdkEventButton * ) [inline], [private]
Simply returns false.
12.66.3 Field Documentation
12.66.3.1 m_seq
sequence& seq64::seqtime::m_seq [private]
12.66.3.2 m_scroll_offset_ticks
int seq64::seqtime::m_scroll_offset_ticks [private]
12.66.3.3 m_scroll_offset_x
int seq64::seqtime::m_scroll_offset_x [private]
12.66.3.4 m_zoom
int seq64::seqtime::m_zoom [private]
12.66.3.5 m_ppqn
int seq64::seqtime::m_ppqn [private]
```

12.67 seq64::sequence Class Reference

The sequence class is firstly a receptable for a single track of MIDI data read from a MIDI file or edited into a pattern.

Public Types

```
enum select_action_e {
e_select,
e_select_one,
e_is_selected,
e_would_select,
e_deselect,
e_toggle_selection,
e_remove_one }
```

This enumeration is used in selecting events and note.

Public Member Functions

• sequence (int ppgn=SEQ64 USE DEFAULT PPQN)

Principal constructor.

∼sequence ()

A rote destructor.

void partial_assign (const sequence &rhs)

A cut-down version of principal assignment operator.

· event_list & events ()

'Getter' function for member m_events

· const event_list & events () const

'Getter' function for member m_events

• bool any selected notes () const

'Getter' function for member m_events.any_selected_notes()

• const triggers::List & triggerlist () const

'Getter' function for member m_triggers This is the const version.

• triggers::List & triggerlist ()

'Getter' function for member m_triggers

• int get_trigger_count () const

Gets the trigger count, useful for exporting a sequence.

- void set_trigger_paste_tick (midipulse tick)
- midipulse get_trigger_paste_tick () const
- int number () const

'Getter' function for member m_seq_number

• void number (int seqnum)

'Setter' function for member m_seq_number This setter will set the sequence number only if it has not already been set.

• void modify ()

A convenience function that we have to put here so that the m_parent pointer can be used without an additional include-file in the sequence.hpp module.

• int event count () const

Returns the number of events stored in m_events.

void set_hold_undo (bool hold)

Modifies the undo-hold container.

• int get_hold_undo () const

'Getter' function for member m_events_undo_hold.count()

void set_have_undo ()

'Setter' function for member m_have_undo

bool have_undo () const

'Getter' function for member m_have_undo

void set_have_redo ()

'Setter' function for member m_have_redo No reliable way to "unmodify" the performance here.

· bool have_redo () const

'Getter' function for member m_have_redo

void push_undo (bool hold=false)

Pushes the event-list into the undo-list or the upcoming undo-hold-list.

void pop undo ()

If there are items on the undo list, this function pushes the event-list into the redo-list, puts the top of the undo-list into the event-list, pops from the undo-list, calls verify_and_link(), and then calls unselect.

void pop_redo ()

If there are items on the redo list, this function pushes the event-list into the undo-list, puts the top of the redo-list into the event-list, pops from the redo-list, calls verify and link(), and then calls unselect.

void push trigger undo ()

Calls triggers::push_undo() with locking.

• void pop_trigger_undo ()

Calls triggers::pop_undo() with locking.

- void pop trigger redo ()
- void set_name (const std::string &name)

Sets the sequence name member, m name.

void set_name (char *name)

Sets the sequence name member, m_name.

- · void set_measures (int lengthmeasures)
- int get measures ()
- int get ppqn () const

'Getter' function for member m_ppqn Provided as a convenience for the editable_events class.

void set_beats_per_bar (int beatspermeasure)

'Setter' function for member m time beats per measure

• int get_beats_per_bar () const

'Getter' function for member m_time_beats_per_measure

void set_beat_width (int beatwidth)

'Setter' function for member m time beat width

int get_beat_width () const

'Getter' function for member m_time_beat_width

• midipulse measures_to_ticks (int measures=1) const

A convenience function for calculating the number of ticks in the given number of measures.

void clocks_per_metronome (int cpm)

'Setter' function for member m_clocks_per_metronome

int clocks_per_metronome () const

'Getter' function for member m_clocks_per_metronome

void set_32nds_per_quarter (int tpq)

'Setter' function for member m_32nds_per_quarter

int get_32nds_per_quarter () const

'Getter' function for member m_32nds_per_quarter

void us_per_quarter_note (long upqn)

'Setter' function for member m_us_per_quarter_note

long us_per_quarter_note () const

'Getter' function for member m_us_per_quarter_note

void set_rec_vol (int rec_vol)

'Setter' function for member m_rec_vol If this velocity is greater than zero, then m_note_on_velocity will be set as well.

• void set_song_mute (bool mute)

'Setter' function for member m_song_mute This function also calls set_dirty_mp() to make sure that the perfnames panel is updated to show the new mute status of the sequence.

void toggle_song_mute ()

'Setter' function for member m_song_mute This function toogles the song muting status.

• bool get_song_mute () const

'Getter' function for member m_song_mute

void apply_song_transpose ()

Applies the transpose value held by the master MIDI buss object, if non-zero, and if the sequence is set to be transposable.

void set transposable (bool flag)

'Setter' function for member m_transposable Changing this flag modifies the sequence and performance.

• bool get_transposable () const

'Getter' function for member m_transposable

• const char * get name () const

'Getter' function for member m_name pointer

• const std::string & name () const

'Getter' function for member m_name

void set_editing (bool edit)

'Setter' function for member m_editing

bool get_editing () const

'Getter' function for member m_editing

void set_raise (bool edit)

'Setter' function for member m_raise

· bool get raise (void) const

'Getter' function for member m_raise

• void set_length (midipulse len, bool adjust_triggers=true)

Sets the length (m_length) and adjusts triggers for it, if desired.

midipulse get_length () const

'Getter' function for member m_length

midipulse get last tick ()

Returns the last tick played, and is used by the editor's idle function.

void set_last_tick (midipulse tick)

'Setter' function for member m_last_tick This function used to be called "set_orig_tick()", now renamed to match up with get_last_tick().

• midipulse mod last tick ()

Some MIDI file errors and other things can lead to an m_length of 0, which causes arithmetic errors when m_last_tick is modded against it.

void set_playing (bool)

Sets the playing state of this sequence.

bool get_playing () const

'Getter' function for member m_playing

• void toggle_playing ()

Toggles the playing status of this sequence.

void toggle_queued ()

'Setter' function for member m_queued and m_queued_tick Toggles the queued flag and sets the dirty-mp flag.

• void off queued ()

'Setter' function for member m_queued Turns off (resets) the queued flag and sets the dirty-mp flag.

void on_queued ()

'Setter' function for member m_queued Turns on (sets) the queued flag and sets the dirty-mp flag.

• bool get_queued () const

'Getter' function for member m_queued

midipulse get_queued_tick () const

'Getter' function for member m_queued_tick

bool check_queued_tick (midipulse tick) const

Helper function for perform.

void set_recording (bool)

'Setter' function for member m_recording and m_notes_on

· bool get recording () const

'Getter' function for member m_recording

void set_snap_tick (int st)

'Setter' function for member m_snap_tick

void set_quantized_rec (bool qr)

'Setter' function for member m_quantized_rec

bool get_quantized_rec () const

'Getter' function for member m_quantized_rec

void set thru (bool)

'Setter' function for member m_thru

• bool get_thru () const

'Getter' function for member m thru

bool is_dirty_main ()

Returns the value of the dirty main flag, and sets that flag to false (i.e.

· bool is_dirty_edit ()

Returns the value of the dirty edit flag, and sets that flag to false.

bool is_dirty_perf ()

Returns the value of the dirty performance flag, and sets that flag to false.

bool is_dirty_names ()

Returns the value of the dirty names (heh heh) flag, and sets that flag to false.

void set_dirty_mp ()

Sets the dirty flags for names, main, and performance.

· void set_dirty ()

Call set_dirty_mp() and then sets the dirty flag for editing.

• midibyte get_midi_channel () const

'Getter' function for member m_midi_channel

• bool is_smf_0 () const

Returns true if this sequence is an SMF 0 sequence.

• void set_midi_channel (midibyte ch, bool user_change=false)

Sets the m_midi_channel number>

· void print () const

Prints a list of the currently-held events.

· void print_triggers () const

Prints a list of the currently-held triggers.

• void play (midipulse tick, bool playback mode)

The play() function dumps notes starting from the given tick, and it pre-buffers ahead.

void play_queue (midipulse tick, bool playbackmode)

Provides encapsulation for a series of called used in perform::play().

bool add event (const event &er)

Adds an event to the internal event list in a sorted manner.

void add_trigger (midipulse tick, midipulse len, midipulse offset=0, bool adjust_offset=true)

Adds a trigger.

· void split trigger (midipulse tick)

Splits a trigger.

• void grow_trigger (midipulse tick_from, midipulse tick_to, midipulse len)

Grows a trigger.

void del_trigger (midipulse tick)

Deletes a trigger, that brackets the given tick, from the trigger-list.

bool get_trigger_state (midipulse tick)

Checks the list of triggers against the given tick.

· bool select_trigger (midipulse tick)

Checks the list of triggers against the given tick.

· triggers::List get_triggers () const

Returns a copy of the triggers for this sequence.

bool unselect_triggers ()

Unselects all triggers.

bool intersect_triggers (midipulse position, midipulse &start, midipulse &ender)

This function examines each trigger in the trigger list.

• bool intersect_notes (midipulse position, midipulse position_note, midipulse &start, midipulse &ender, int ¬e)

This function examines each note in the event list.

bool intersect events (midipulse posstart, midipulse posend, midibyte status, midipulse &start)

This function examines each non-note event in the event list.

• void del selected trigger ()

Deletes the first selected trigger that is found.

void cut_selected_trigger ()

Copies and deletes the first selected trigger that is found.

void copy_selected_trigger ()

First, this function clears any unpasted middle-click tick setting.

void paste_trigger (midipulse paste_tick=SEQ64_NO_PASTE_TRIGGER)

If there is a copied trigger, then this function grabs it from the trigger clipboard and adds it.

bool move_selected_triggers_to (midipulse tick, bool adjust_offset, triggers::grow_edit_t which=triggers::G←
 ROW MOVE)

Moves selected triggers as per the given parameters.

• midipulse selected_trigger_start ()

Gets the last-selected trigger's start tick.

• midipulse selected_trigger_end ()

Gets the selected trigger's end tick.

midipulse get_max_trigger ()

Get the ending value of the last trigger in the trigger-list.

• void move_triggers (midipulse start_tick, midipulse distance, bool direction)

Moves triggers in the trigger-list.

void copy_triggers (midipulse start_tick, midipulse distance)

Copies triggers to another location.

• void clear_triggers ()

Clears the whole list of triggers.

midipulse get_trigger_offset () const

'Getter' function for member m_trigger_offset

void set_midi_bus (char mb, bool user_change=false)

Sets the MIDI buss/port number to dump MIDI data to.

char get_midi_bus () const

'Getter' function for member m_bus

void set master midi bus (mastermidibus *mmb)

'Setter' function for member m_masterbus Do we need to call set_dirty_mp() here?

• int select note events (midipulse tick s, int note h, midipulse tick f, int note l, select action e action)

Selects events in range provided: tick start, note high, tick end, and note low.

• int select_events (midipulse tick_s, midipulse tick_f, midibyte status, midibyte cc, select_action_e action)

Select all events in the given range, and returns the number selected.

• int select_events (midibyte status, midibyte cc, bool inverse=false)

int select_events (midipulse tick_s, midipulse tick_f, midibyte status)

Select all events with the given status, and returns the number selected.

• int select_event_handle (midipulse tick_s, midipulse tick_f, midibyte status, midibyte cc, int data_s)

Use selected note ons if any.

int select linked (long tick s, long tick f, midibyte status)

Used with seqevent when selecting Note On or Note Off, this function will select the opposite linked event.

- int select_even_or_odd_notes (int note_len, bool even)
- void select_all_notes (bool inverse=false)

New convenience function.

int get_num_selected_notes () const

Counts the selected notes in the event list.

int get_num_selected_events (midibyte status, midibyte cc) const

Counts the selected events, with the given status, in the event list.

• void select all ()

Selects all events, unconditionally.

void copy selected ()

Copies the selected events.

void cut selected (bool copyevents=true)

Cuts the selected events.

void paste selected (midipulse tick, int note)

Pastes the selected notes (and only note events) at the given tick and the given note value.

• void get_selected_box (midipulse &tick_s, int ¬e_h, midipulse &tick_f, int ¬e_l)

Returns the 'box' of the selected items.

void get_clipboard_box (midipulse &tick_s, int ¬e_h, midipulse &tick_f, int ¬e_l)

Returns the 'box' of the clipboard items.

· midipulse adjust_timestamp (midipulse t, bool isnoteoff)

A new function to consolidate the adjustment of timestamps in a pattern.

midipulse trim_timestamp (midipulse t)

A new function to consolidate the adjustment of timestamps in a pattern.

• midipulse clip_timestamp (midipulse ontime, midipulse offtime)

A new function to consolidate the growth/shrinkage of timestamps in a pattern.

void move_selected_notes (midipulse deltatick, int deltanote)

Removes and adds selected notes in position.

void add note (midipulse tick, midipulse len, int note, bool paint=false)

Adds a note of a given length and note value, at a given tick location.

void add_chord (int chord, midipulse tick, midipulse len, int note)

Adds a chord of a given length and note value, at a given tick location.

void add_event (midipulse tick, midibyte status, midibyte d0, midibyte d1, bool paint=false)

Adds a event of a given status value and data values, at a given tick location.

bool stream_event (event &ev)

Streams the given event.

bool change_event_data_range (midipulse tick_s, midipulse tick_f, midibyte status, midibyte cc, int d_s, int d f)

Changes the event data range.

- void change_event_data_lfo (double value, double range, double speed, double phase, wave_type_t wave, midibyte status, midibyte cc)
- void increment_selected (midibyte status, midibyte)

Increments events the match the given status and control values.

· void decrement_selected (midibyte status, midibyte)

Decrements events the match the given status and control values.

void grow selected (midipulse deltatick)

The original description was "Moves note off event." But this also gets called when simply selecting a second note via a ctrl-left-click, even in seq24.

void stretch_selected (midipulse deltatick)

Performs a stretch operation on the selected events.

• bool remove marked ()

Removes marked events.

bool mark_selected ()

Marks the selected events.

• void remove selected ()

Removes selected events.

void unpaint_all ()

Unpaints all events in the event-list.

· void unselect ()

Deselects all events, unconditionally.

void verify and link ()

This function verifies state: all note-ons have a note-off, and it links note-offs with their note-ons.

void link_new ()

Links a new event.

• void zero_markers ()

Resets everything to zero.

• void play_note_on (int note)

Plays a note from the piano roll on the main bus on the master MIDI buss.

• void play_note_off (int note)

Turns off a note from the piano roll on the main bus on the master MIDI buss.

void off_playing_notes ()

Sends a note-off event for all active notes.

• void pause ()

A pause version of reset().

· void reset (bool live_mode)

Provides a helper function simplify and speed up perform::reset_sequences().

• void reset_draw_marker ()

This refreshes the play marker to the last tick.

void reset_draw_trigger_marker ()

Sets the draw-trigger iterator to the beginning of the trigger list.

draw_type_t get_next_note_event (midipulse *tick_s, midipulse *tick_f, int *note, bool *selected, int *velocity)

Each call to seqdata() fills the passed references with a events elements, and returns true.

bool get_minmax_note_events (int &lowest, int &highest)

A new function provided so that we can find the minimum and maximum notes with only one (not two) traversal of the event list.

bool get_next_event (midibyte status, midibyte cc, midipulse *tick, midibyte *d0, midibyte *d1, bool *selected, int evtype=EVENTS ALL)

Get the next event in the event list that matches the given status and control character.

• bool get_next_event (midibyte *status, midibyte *cc)

Get the next event in the event list.

bool get_next_trigger (midipulse *tick_on, midipulse *tick_off, bool *selected, midipulse *tick_offset)

Get the next trigger in the trigger list, and set the parameters based on that trigger.

• void quantize_events (midibyte status, midibyte cc, midipulse snap_tick, int divide, bool linked=false)

Grabs the specified events, puts them into a list, quantizes them against the snap ticks, and merges them in to the event container.

void push_quantize (midibyte status, midibyte cc, midipulse snap_tick, int divide, bool linked=false)

A new convenience function.

void transpose notes (int steps, int scale)

Transposes notes by the given steps, in accordance with the given scale.

- · void shift notes (midipulse ticks)
- void multiply_pattern (double multiplier)
- · midibyte musical_key () const

'Getter' function for member m_musical_key

void musical_key (int key)

'Setter' function for member m_musical_key

• midibyte musical_scale () const

'Getter' function for member m_musical_scale

void musical_scale (int scale)

'Setter' function for member m musical scale

int background_sequence () const

'Getter' function for member m_background_sequence

· void background_sequence (int bs)

'Setter' function for member m_background_sequence Only partial validation at present, we do not want the upper limit to be hard-wired at this time.

· void show_events () const

A member function to dump a summary of events stored in the event-list of a sequence.

void copy_events (const event_list &newevents)

Copies an external container of events into the current container, effectively replacing all of its events.

midipulse note_off_margin () const

'Getter' function for member m_note_length

Private Types

typedef std::stack< event_list > EventStack

Provides a stack of event-lists for use with the undo and redo facility.

Private Member Functions

- sequence & operator= (const sequence &rhs)
- bool event in range (const event &e, midibyte status, midipulse tick s, midipulse tick f) const

A convenience function used a couple of times.

void set_parent (perform *p)

'Setter' function for member m_parent Sets the "parent" of this sequence, so that it can get some extra information about the performance.

void put_event_on_bus (event &ev)

Takes an event that this sequence is holding, and places it on the MIDI buss.

void set_trigger_offset (midipulse trigger_offset)

Sets m_trigger_offset and wraps it to m_length.

void adjust_trigger_offsets_to_length (midipulse newlen)

Adjusts trigger offsets to the length specified for all triggers, and undo triggers.

- · midipulse adjust_offset (midipulse offset)
- void remove (event list::iterator i)

A helper function, which does not lock/unlock, so it is unsafe to call without supplying an iterator from the event-list.

· void remove (event &e)

A helper function, which does not lock/unlock, so it is unsafe to call without supplying an iterator from the event-list.

· void remove_all ()

Clears all events from the event container.

· bool channel_match (const event &e) const

Checks to see if the event's channel matches the sequence's nominal channel.

Private Attributes

• perform * m_parent

For pause support, we need a way for the sequence to find out if JACK transport is active.

· event list m events

This list holds the current pattern/sequence events.

· triggers m_triggers

The triggers associated with the sequence, used in the performance/song editor.

event_list m_events_undo_hold

Provides a list of event actions to undo for the Stazed LFO and segdata support.

· bool m have undo

A stazed flag indicating that we have some undo information.

bool m_have_redo

A stazed flag indicating that we have some redo information.

· EventStack m events undo

Provides a list of event actions to undo.

EventStack m_events_redo

Provides a list of event actions to redo.

event_list::iterator m_iterator_draw

An iterator for drawing events.

bool m_channel_match

A new feature for recording, based on a "stazed" feature.

· midibyte m midi channel

Contains the proper MIDI channel for this sequence.

midibyte m_bus

Contains the proper MIDI bus number for this sequence.

· bool m song mute

Provides a flag for the song playback mode muting.

bool m_transposable

Indicate if the sequence is transposable or not.

• int m_notes_on

Provides a member to hold the polyphonic step-edit note counter.

• mastermidibus * m masterbus

Provides the master MIDI buss which handles the output of the sequence to the proper buss and MIDI channel.

int m_playing_notes [SEQ64_MIDI_NOTES_MAX]

Provides a "map" for Note On events.

· bool m was playing

Indicates if the sequence was playing.

bool m_playing

True if sequence playback currently is in progress for this sequence.

· bool m recording

True if sequence recording currently is in progress for this sequence.

• bool m_quantized_rec

True if recoring in quantized mode.

bool m_thru

True if recoring in MIDI-through mode.

· bool m queued

True if the events are queued.

· bool m_dirty_main

These flags indicate that the content of the sequence has changed due to recording, editing, performance management, or even (?) a name change.

· bool m dirty edit

Provides the main is-edited flag.

· bool m_dirty_perf

Provides performance dirty flagflag.

bool m_dirty_names

Provides the names dirtiness flag.

bool m_editing

Indicates that the sequence is currently being edited.

bool m_raise

Used in seqmenu and seqedit.

• std::string m_name

Provides the name/title for the sequence.

midipulse m_last_tick

These members manage where we are in the playing of this sequence, including triggering.

• midipulse m_queued_tick

Provides the next tick to play?

midipulse m_trigger_offset

Provides the trigger offset.

const int m_maxbeats

This constant provides the scaling used to calculate the time position in ticks (pulses), based also on the PPQN value.

• int m_ppqn

Holds the PPQN value for this sequence, so that we don't have to rely on a global constant value.

· int m seq number

A new member so that the sequence number is carried along with the sequence.

• midipulse m_length

Holds the length of the sequence in pulses (ticks).

• midipulse m_snap_tick

The size of snap in units of pulses (ticks).

• int m_time_beats_per_measure

Provides the number of beats per bar used in this sequence.

int m_time_beat_width

Provides with width of a beat.

int m_clocks_per_metronome

Augments the beats/bar and beat-width with the additional values included in a Time Signature meta event.

int m_32nds_per_quarter

Augments the beats/bar and beat-width with the additional values included in a Time Signature meta event.

· long m us per quarter note

Augments the beats/bar and beat-width with the additional values included in a Tempo meta event.

int m_rec_vol

The volume to be used when recording.

• int m_note_on_velocity

The Note On velocity used.

int m_note_off_velocity

The Note Off velocity used.

midibyte m_musical_key

Holds a copy of the musical key for this sequence, which we now support writing to this sequence.

• midibyte m_musical_scale

Holds a copy of the musical scale for this sequence, which we now support writing to this sequence.

• int m_background_sequence

Holds a copy of the background sequence number for this sequence, which we now support writing to this sequence.

· mutex m mutex

Provides locking for the sequence.

• const midipulse m_note_off_margin

Provides the number of ticks to shave off of the end of painted notes.

Static Private Attributes

• static event_list m_events_clipboard

A static clipboard for holding pattern/sequence events.

Friends

- · class perform
- · class triggers

12.67.1 Detailed Description

More members than you can shake a stick at.

12.67.2 Member Typedef Documentation

12.67.2.1 EventStack

```
typedef std::stack<event_list> seq64::sequence::EventStack [private]
```

12.67.3 Member Enumeration Documentation

12.67.3.1 select_action_e

```
enum seq64::sequence::select_action_e
```

Se the select_note_events() and select_events() functions.

Enumerator

e_select	Selection in progress.
e_select_one	To select a single event.
e_is_selected	The events are selected.
e_would_select	The events would be selected.
e_deselect	To deselect event under the cursor.
e_toggle_selection	Toggle selection under cursor.
e_remove_one	To remove one note under the cursor.

12.67.4 Constructor & Destructor Documentation

12.67.4.1 sequence()

Parameters

ppqn | Provides the PPQN parameter to perhaps alter the default PPQN value of this sequence.

```
12.67.4.2 \sim sequence()
```

```
seq64::sequence::~sequence ( )
```

12.67.5 Member Function Documentation

12.67.5.1 operator=()

12.67.5.2 partial_assign()

We're replacing that incomplete function (many members are not assigned) with the more accurately-named partial_assign() function.

It did not assign them all, so we created this partial_assign() function to do this work, and replaced operator =() with this function in client code.

Threadsafe

Parameters

ns Provides the source of the new member values.

```
12.67.5.3 events() [1/2]
event_list& seq64::sequence::events ( ) [inline]

12.67.5.4 events() [2/2]
const event_list& seq64::sequence::events ( ) const [inline]
```

```
12.67.5.5 any_selected_notes()
bool seq64::sequence::any_selected_notes ( ) const [inline]
12.67.5.6 triggerlist() [1/2]
const triggers::List& seq64::sequence::triggerlist ( ) const [inline]
12.67.5.7 triggerlist() [2/2]
triggers::List& seq64::sequence::triggerlist ( ) [inline]
12.67.5.8 get_trigger_count()
int seq64::sequence::get_trigger_count ( ) const [inline]
12.67.5.9 set_trigger_paste_tick()
void seq64::sequence::set_trigger_paste_tick (
             midipulse tick ) [inline]
12.67.5.10 get_trigger_paste_tick()
midipulse seq64::sequence::get_trigger_paste_tick ( ) const [inline]
12.67.5.11 number() [1/2]
int seq64::sequence::number ( ) const [inline]
12.67.5.12 number() [2/2]
void seq64::sequence::number (
             int seqnum ) [inline]
12.67.5.13 modify()
void seq64::sequence::modify ( )
```

One minor issue is how can we unmodify the performance? We'd need to keep a count/stack of modifications over all sequences in the performance. Probably not practical, in general. We will probably keep track of the modification of the buss (port) and channel numbers, as per GitHub Issue #47..

12.67.5.14 event_count()

```
int seq64::sequence::event_count ( ) const
```

Note that only playable events are counted in a sequence. If a sequence class function provides a mutex, call m_events.count() instead.

Threadsafe

Returns

Returns m_events.count().

12.67.5.15 set_hold_undo()

```
void seq64::sequence::set_hold_undo (
          bool hold )
```

Parameters

hold

If true, then the events in the m_events container are added to the m_events_undo_hold container. Otherwise, that container is cleared.

```
12.67.5.16 get_hold_undo()
```

Threadsafe

Parameters

hold

A new parameter for the stazed undo/redo support, not yet used. If true, then the events go into the undo-hold-list.

```
12.67.5.22 pop_undo()

void seq64::sequence::pop_undo ( )
```

We would like to be able to set perform's modify flag to false here, but other sequences might still be in a modified state. We could add a modify flag to sequence, and falsify that flag here. Something to think about.

Threadsafe

```
12.67.5.23 pop_redo()
void seq64::sequence::pop_redo ( )
Threadsafe
12.67.5.24 push_trigger_undo()
void seq64::sequence::push_trigger_undo ( )
Threadsafe
12.67.5.25 pop_trigger_undo()
void seq64::sequence::pop_trigger_undo ( )
12.67.5.26 pop_trigger_redo()
void seq64::sequence::pop_trigger_redo ( )
12.67.5.27 set_name() [1/2]
void seq64::sequence::set_name (
             const std::string & name )
12.67.5.28 set_name() [2/2]
void seq64::sequence::set_name (
```

char * name)

```
12.67.5.29 set_measures()
void seq64::sequence::set_measures (
             int lengthmeasures )
12.67.5.30 get_measures()
int seq64::sequence::get_measures ( )
12.67.5.31 get_ppqn()
int seq64::sequence::get_ppqn ( ) const [inline]
12.67.5.32 set_beats_per_bar()
void seq64::sequence::set_beats_per_bar (
            int beatspermeasure )
Threadsafe
Parameters
 beatspermeasure
                    The new setting of the beats-per-bar value.
12.67.5.33 get_beats_per_bar()
int seq64::sequence::get_beats_per_bar ( ) const [inline]
12.67.5.34 set_beat_width()
void seq64::sequence::set_beat_width (
             int beatwidth )
Threadsafe
Parameters
 beatwidth
             The new setting of the beat width value.
12.67.5.35 get_beat_width()
int seq64::sequence::get_beat_width ( ) const [inline]
```

```
12.67.5.36 measures_to_ticks()
midipulse seq64::sequence::measures_to_ticks (
            int measures = 1 ) const [inline]
12.67.5.37 clocks_per_metronome() [1/2]
void seq64::sequence::clocks_per_metronome (
             int cpm ) [inline]
12.67.5.38 clocks_per_metronome() [2/2]
int seq64::sequence::clocks_per_metronome ( ) const [inline]
12.67.5.39 set_32nds_per_quarter()
void seq64::sequence::set_32nds_per_quarter (
             int tpq ) [inline]
12.67.5.40 get_32nds_per_quarter()
int seq64::sequence::get_32nds_per_quarter ( ) const [inline]
12.67.5.41 us_per_quarter_note() [1/2]
void seq64::sequence::us_per_quarter_note (
             long upqn ) [inline]
12.67.5.42 us_per_quarter_note() [2/2]
long seq64::sequence::us_per_quarter_note ( ) const [inline]
12.67.5.43 set_rec_vol()
void seq64::sequence::set_rec_vol (
             int recvol )
```

Threadsafe

Parameters

recvol	The new setting of the recording volume setting. It is used only if it ranges from 0 to
	SEQ64_MAX_NOTE_ON_VELOCITY.

```
12.67.5.44 set_song_mute()
void seq64::sequence::set_song_mute (
            bool mute ) [inline]
12.67.5.45 toggle_song_mute()
void seq64::sequence::toggle_song_mute ( ) [inline]
12.67.5.46 get_song_mute()
bool seq64::sequence::get_song_mute ( ) const [inline]
12.67.5.47 apply_song_transpose()
void seq64::sequence::apply_song_transpose ( )
12.67.5.48 set_transposable()
void seq64::sequence::set_transposable (
            bool flag )
Note that when a sequence is being read from a MIDI file, it will not yet have a parent, so we have to check for that
before setting the perform modify flag.
12.67.5.49 get_transposable()
bool seq64::sequence::get_transposable ( ) const [inline]
12.67.5.50 get_name()
const char* seq64::sequence::get_name ( ) const [inline]
Deprecated
12.67.5.51 name()
const std::string& seq64::sequence::name ( ) const [inline]
12.67.5.52 set_editing()
void seq64::sequence::set_editing (
             bool edit ) [inline]
```

This function is called in seqedit::apply_length(), when the user selects a sequence length in measures. That function calculates the length in ticks:

```
L = M x B x 4 x P / W
L == length (ticks or pulses)
M == number of measures
B == beats per measure
P == pulses per quarter-note
W == beat width in beats per measure

For our "b4uacuse" MIDI file, M can be about 100 measures, B is 4, P can be 192 (but we want to support higher values), and W is 4. So L = 100 * 4 * 4 * 192 / 4 = 76800 ticks. Seems small.

Threadsafe

12.67.5.57 get_length()
midipulse seq64::sequence::get_length ( ) const [inline]
12.67.5.58 get_last_tick()
```

midipulse seq64::sequence::get_last_tick ()

If m_length is 0, this function returns m_last_tick - m_trigger_offset, to avoid an arithmetic exception. Should we return 0 instead?

Note that seqroll calls this function to help get the location of the progress bar. What does perfedit do?

When playing, and the sequencer is running, notes get dumped to the ALSA buffers.

Parameters

p Provides the playing status to set. True means to turn on the playing, false means to turn it off, and turn off any notes still playing.

```
12.67.5.62 get_playing()
```

```
bool seq64::sequence::get_playing ( ) const [inline]
```

12.67.5.63 toggle_playing()

```
void seq64::sequence::toggle_playing ( ) [inline]
```

How exactly does this differ from toggling the mute status?

12.67.5.64 toggle_queued()

```
void seq64::sequence::toggle_queued ( )
```

Also calculates the queued tick based on m_last_tick.

```
12.67.5.65 off_queued()
void seq64::sequence::off_queued ( )
Do we need to set m_queued_tick as in toggle_queued()? Currently not used.
Threadsafe
12.67.5.66 on_queued()
void seq64::sequence::on_queued ( )
Do we need to set m_queued_tick as in toggle_queued()? Currently not used.
Threadsafe
12.67.5.67 get_queued()
bool seq64::sequence::get_queued ( ) const [inline]
12.67.5.68 get_queued_tick()
midipulse seq64::sequence::get_queued_tick ( ) const [inline]
12.67.5.69 check_queued_tick()
bool seq64::sequence::check_queued_tick (
             midipulse tick ) const [inline]
12.67.5.70 set_recording()
void seq64::sequence::set_recording (
             bool r )
Threadsafe
12.67.5.71 get_recording()
bool seq64::sequence::get_recording ( ) const [inline]
12.67.5.72 set_snap_tick()
void seq64::sequence::set_snap_tick (
             int st )
```

```
12.67.5.73 set_quantized_rec()
void seq64::sequence::set_quantized_rec (
             bool qr )
Threadsafe
12.67.5.74 get_quantized_rec()
bool seq64::sequence::get_quantized_rec ( ) const [inline]
12.67.5.75 set_thru()
void seq64::sequence::set_thru (
             bool r )
Threadsafe
12.67.5.76 get_thru()
bool seq64::sequence::get_thru ( ) const [inline]
12.67.5.77 is_dirty_main()
bool seq64::sequence::is_dirty_main ( )
resets it). This flag signals that a redraw is needed from recording.
Threadsafe
Returns
     Returns the dirty status.
12.67.5.78 is_dirty_edit()
bool seq64::sequence::is_dirty_edit ( )
The m_dirty_edit flag is set by the function set_dirty().
Threadsafe
Returns
```

Returns the dirty status.

```
12.67.5.79 is_dirty_perf()
bool seq64::sequence::is_dirty_perf ( )
Threadsafe
Returns
     Returns the dirty status.
12.67.5.80 is_dirty_names()
bool seq64::sequence::is_dirty_names ( )
Not sure that we need to lock a boolean on modern processors.
Threadsafe
Returns
     Returns the dirty status.
12.67.5.81 set_dirty_mp()
void seq64::sequence::set_dirty_mp ( )
These flags are meant for causing user-interface refreshes, not for performance modification.
m_dirty_names is set to false in is_dirty_names(); m_dirty_names is set to false in is_dirty_main(); m_dirty_names
is set to false in is_dirty_perf().
Not threadsafe
12.67.5.82 set_dirty()
void seq64::sequence::set_dirty ( )
Threadsafe
12.67.5.83 get_midi_channel()
midibyte seq64::sequence::get_midi_channel ( ) const [inline]
12.67.5.84 is_smf_0()
bool seq64::sequence::is_smf_0 ( ) const [inline]
12.67.5.85 set_midi_channel()
void seq64::sequence::set_midi_channel (
              midibyte ch,
              bool user_change = false )
```

ch	The MIDI channel to set as the channel number for this sequence.
user_change	If true (the default value is false), the user has decided to change this value, and we might need to modify the perform's dirty flag, so that the user gets prompted for a change, This is a response to GitHub issue #47, where channel changes do not cause a prompt to save the sequence.

This function is called by the sequencer thread, performance. The tick comes in as global tick.

It turns the sequence off after we play in this frame.

Note

With pause support, the progress bar for the pattern/sequence editor does what we want: pause with the pause button, and rewind with the stop button. Works with JACK, with issues, but we'd like to have the stop button do a rewind in JACK, too.

Parameters

tick	Provides the current end-tick value.
playback_mode	Provides how playback is managed. True indicates that it is performance/song-editor playback, controlled by the set of patterns and triggers set up in that editor, and saved with the song in seq24 format. False indicates that the playback is controlled by the main windows, in live mode.

12.67.5.89 play_queue()

```
void seq64::sequence::play_queue (
    midipulse tick,
    bool playbackmode )
```

Starts the playing of a pattern/sequence. This function just has the sequence dump its events. It ignores the sequence if it has no playable MIDI events.

Change Note ca 2016-10-12 Issue #39. Removed the check for a non-zero event count. This lets the seqroll show the progress bar in motion.

Parameters

tick		Provides the tick/pulse from which to start playing.
pla	ybackmode	Indicates if the playback is in live mode (false) or song mode (true).

Then it reset the draw-marker and sets the dirty flag.

Currently, when reading a MIDI file [see the midifile::parse() function], only the main events (notes, after-touch, pitch, program changes, etc.) are added with this function. So, we can rely on reading only playable events into a sequence. Well, actually, certain meta-events are also read, to obtain channel, buss, and more settings. Also read for a sequence, if the global-sequence flag is not set, are the new key, scale, and background sequence parameters.

This module (sequencer) adds all of those events as well, but it can surely add other events. We should assume that any events added by sequencer are playable/usable.

Here, we could ignore events not on the sequence's channel, as an option. We have to be careful because this function can be used in painting events.

Threadsafe

Warning

This pushing (and, in writing the MIDI file, the popping), causes events with identical timestamps to be written in reverse order. Doesn't affect functionality, but it's puzzling until one understands what is happening. Actually, this is true only in Seq24, we've fixed that behavior for Sequencer64.

Parameters

er Provide a reference to the event to be added; the event is copied into the events container.

Returns

Returns true if the event was added.

12.67.5.91 add_trigger()

A pass-through function that calls triggers::add(). See that function for more details.

Threadsafe

Parameters

tick	The time destination of the trigger.
len	The duration of the trigger.
offset	The performance offset of the trigger.
fixoffset	If true, adjust the offset.

12.67.5.92 split_trigger()

This is the public overload of split_trigger.

Threadsafe

Parameters

splittick	The time location of the split.
-----------	---------------------------------

12.67.5.93 grow_trigger()

See triggers::grow() for more information.

Parameters

tickfrom	The desired from-value back which to expand the trigger, if necessary.
tickto	The desired to-value towards which to expand the trigger, if necessary.
len	The additional length to append to tickto for the check.

12.67.5.94 del_trigger()

See triggers::remove().

Threadsafe

Parameters

tick Provides the tick to be used for finding the trigger to be erased.

12.67.5.95 get_trigger_state()

If any trigger is found to bracket that tick, then true is returned.

Parameters

tick Provides the tick of interest.

Returns

Returns true if a trigger is found that brackets the given tick.

12.67.5.96 select_trigger()

If any trigger is found to bracket that tick, then true is returned, and the trigger is marked as selected.

Parameters

tick | Provides the tick of interest.

Returns

Returns true if a trigger is found that brackets the given tick; this is the return value of m_triggers.select().

12.67.5.97 get_triggers()

```
triggers::List seq64::sequence::get_triggers ( ) const
```

This function is basically a threadsafe version of sequence::triggerlist().

Returns

Returns of copy of m_triggers.triggerlist().

12.67.5.98 unselect_triggers()

```
bool seq64::sequence::unselect_triggers ( )
```

Returns

Returns the m_triggers.unselect() return value.

12.67.5.99 intersect_triggers()

If the given position is between the current trigger's tick-start and tick-end values, the these values are copied to the start and end parameters, respectively, and then we exit. See triggers::intersect().

Threadsafe

Parameters

position	The position to examine.
start	The destination for the starting tick of the matching trigger.
ender	The destination for the ending tick of the matching trigger.

Returns

Returns true if a trigger was found whose start/end ticks contained the position. Otherwise, false is returned, and the start and end return parameters should not be used.

12.67.5.100 intersect_notes()

```
bool seq64::sequence::intersect_notes (
    midipulse position,
    midipulse position_note,
    midipulse & start,
    midipulse & ender,
    int & note )
```

If the given position is between the current notes on and off time values, values, the these values are copied to the start and end parameters, respectively, the note value is copied to the note parameter, and then we exit.

	position	The position to examine.
	position_note	I think this is the note value we might be looking for ???
out	start	The destination for the starting timestamp of the matching note.
out	ender	The destination for the ending timestamp of the matching note.
out	note	The destination for the note of the matching event. Why is this an int value???

Returns

Returns true if a event was found whose start/end ticks contained the position. Otherwise, false is returned, and the start and end return parameters should not be used.

12.67.5.101 intersect_events()

If the given position is between the current notes's timestamp-start and timestamp-end values, the these values are copied to the posstart and posend parameters, respectively, and then we exit.

Threadsafe

Parameters

posstart	The starting position to examine.
posend	The ending position to examine.
status	The desired status value.
start	The destination for the starting timestamp of the matching trigger.

Returns

Returns true if a event was found whose start/end timestamps contained the position. Otherwise, false is returned, and the start and end return parameters should not be used.

12.67.5.102 del_selected_trigger()

```
void seq64::sequence::del_selected_trigger ( )

12.67.5.103 cut_selected_trigger()
```

void seq64::sequence::cut_selected_trigger ()

```
12.67.5.104 copy_selected_trigger()
```

```
void seq64::sequence::copy_selected_trigger ( )
```

Then it copies the first selected trigger that is found.

```
12.67.5.105 paste_trigger()
```

Why isn't this protected by a mutex? We will enable this if anything bad happens, such as a deadlock, or corruption, that we can prove happens here.

Parameters

paste_tick	A new parameter that provides the tick for pasting, or SEQ64_NO_PASTE_TRIGGER (-1) if there
	is none.

12.67.5.106 move_selected_triggers_to()

Threadsafe

Parameters

tick	The tick at which the trigger starts.
adjustoffset	Set to true if the offset is to be adjusted.
which	Selects which movement will be done, as discussed above.

Returns

Returns the value of triggers::move_selected(), which indicate that the movement could be made. Used in Seq24PerfInput::handle_motion_key().

12.67.5.107 selected_trigger_start()

```
midipulse seq64::sequence::selected_trigger_start ( )
```

Threadsafe

Returns

Returns the tick_start() value of the last-selected trigger. If no triggers are selected, then -1 is returned.

12.67.5.108 selected_trigger_end()

```
midipulse seq64::sequence::selected_trigger_end ( )
```

Threadsafe

Returns

Returns the tick_end() value of the last-selected trigger. If no triggers are selected, then -1 is returned.

12.67.5.109 get_max_trigger()

```
midipulse seq64::sequence::get_max_trigger ( )
```

Threadsafe

Returns

Returns the maximum trigger value.

12.67.5.110 move_triggers()

Note the dependence on the m_length member being kept in sync with the parent's value of m_length.

Threadsafe

Parameters

starttick	rttick The current location of the triggers.	
distance	The distance away from the current location to which to move the triggers.	
direction	If true, the triggers are moved forward. If false, the triggers are moved backward.	

12.67.5.111 copy_triggers()

Threadsafe

Parameters

starttick	The current location of the triggers.	
distance	The distance away from the current location to which to copy the triggers.	

12.67.5.112 clear_triggers()

```
void seq64::sequence::clear_triggers ( )
```

Threadsafe

12.67.5.113 get_trigger_offset()

```
midipulse seq64::sequence::get_trigger_offset ( ) const [inline]
```

12.67.5.114 set_midi_bus()

Threadsafe

Parameters

mb	The MIDI buss to set as the buss number for this sequence. Also called the "MIDI port" number.	
user_change	If true (the default value is false), the user has decided to change this value, and we might need to modify the perform's dirty flag, so that the user gets prompted for a change, This is a response to GitHub issue #47, where buss changes do not cause a prompt to save the sequence.	

```
12.67.5.115 get_midi_bus()
```

```
char seq64::sequence::get_midi_bus ( ) const [inline]
```

12.67.5.116 set_master_midi_bus()

Threadsafe

Parameters

mmb Provides a pointer to the master MIDI buss for this sequence. This should be a reference, but isn't, nor is it checked.

12.67.5.117 select_note_events()

Be aware the the event::is_note() function is used, and that it includes Aftertouch events, which generally need to stick with their Note On counterparts.

If a "note" event is detected, then we skip it. This is necessary since channel pressure and control change use d0 for seqdata, and d0 is returned by get_note(). This causes note selection to occasionally select them when their seqdata values are within range of the tick selection. So therefore we want only Note Ons and Note Offs.

Note

The continuation below ("continue") is necessary since channel pressure and control change use d0 for sequata [which is returned by get_note()]. This causes seqroll note selection to occasionally select them when their sequata values are within the range of tick selection. So only, note ons and offs. What about Aftertouch? We have the event::is_note() function for that.

Parameters

tick_s	The starting tick.
note⊷	The highest note selected.
_h	
tick_f	The ending, or finishing, tick.
note⊷	The lowest note selected.
_/	
action	The action to perform on the selection.

12.67.5.118 select_events() [1/3]

Note that there is also an overloaded version of this function.

tick←	The start time of the selection.		
_s			
tick←	The finish time of the selection.		
_f			
status	The desired event in the selection.		
сс	The desired control-change in the selection, if the event is a control-change.		
action	The desired selection action.		

Returns

Returns the number of events selected.

Note that there is also an overloaded version of this function.

Threadsafe

Warning

This used to be a void function, so it just returns 0 for now.

Parameters

status Provides the status value to be selected.		
СС	If the status is EVENT_CONTROL_CHANGE, then data byte 0 must match this value.	
inverse	If true, invert the selection.	

Returns

Always returns 0.

12.67.5.121 select_event_handle()

```
int seq64::sequence::select_event_handle (
    midipulse tick_s,
    midipulse tick_f,
    midibyte status,
    midibyte cc,
    int data_s )
```

12.67.5.122 select_linked()

12.67.5.123 select_even_or_odd_notes()

12.67.5.124 select_all_notes()

```
void seq64::sequence::select_all_notes (
    bool inverse = false ) [inline]
```

What about Aftertouch events? I think we need to select them as well in seqedit, so let's add that selection here as well.

Parameters

inverse If set to true (the default is false), then this causes the selection to be inverted.

12.67.5.125 get_num_selected_notes()

```
int seq64::sequence::get_num_selected_notes ( ) const
```

Threadsafe

Returns

Returns m_events.count_selected_notes().

12.67.5.126 get_num_selected_events()

If the event is a control change (CC), then it must also match the given CC value.

Threadsafe

Parameters

status	The desired kind of event to count.	
cc	The desired control-change to count, if the event is a control-change.	

Returns

Returns m_events.count_selected_events().

```
12.67.5.127 select_all()
void seq64::sequence::select_all ( )
Threadsafe

12.67.5.128 copy_selected()
void seq64::sequence::copy_selected ( )
```

This function also has the danger, discovered by user 0rel, of events being modified after being added to the clipboard. So we add his reconstruction fix here as well. To summarize the steps:

```
-# Clear the m_events_clipboard. NO! If we have no events to
    copy to the clipboard, we do not want to clear it. This kills
    cut-and-paste functionality.
-# Add all selected events in this clipboard to the sequence.
-# Normalize the timestamps of the events in the clip relative to the
    timestamp of the first selected event. (Is this really needed?)
-# Reconstruct/reconstitute the m_events_clipboard.
```

This process is a bit easier to manage than erase/insert on events because std::multimap has no erase() function that returns the next valid iterator. Also, we use a local clipboard first, to save on copying. We've enhanced the error-checking, too.

Finally, note that m_events_clipboard is a static member of sequence, so:

```
-# Copying can be done between sequences.
-# Access to it needs to be protected by a mutex.
```

Threadsafe

12.67.5.129 cut_selected()

Pushes onto the undo stack, may copy the events, marks the selected events, and removes them. Now also sets the dirty flag so that the caller doesn't have to. Also raises the modify flag on the parent perform object.

copyevents	If true, copy the selected events before marking and removing them.
------------	---

12.67.5.130 paste_selected()

Also, we've moved external calls to push_undo() into this function. The caller shouldn't have to do that.

The event_keys used to access/sort the multimap event_list is not updated after changing timestamp/rank of the stored events. Regenerating all key/value pairs before merging them solves this issue, so that the order of events in the sequence will be preserved. This action is not needed for moving or growing events. Nor is it needed if the old std::list implementation of the event container is compiled in. However, it is needed in any operation that modifies the timestamp of an event inside the container:

```
- copy_selected()
- paste_selected()
- quantize_events() TODO TODO TODO!
```

The alternative to reconstructing the map is to erase-and-insert the events modified in the code above, rather than just tweaking their values, which have an effect on sorting for the event-map implementation. However, multimap does not provide an erase() function that returns the next valid iterator, which would complicate this method of operation. So we're inclined to stick with this solution.

There was an issue with copy/pasting a whole sequence. The pasted events did not go to their destination, but overlayed the original events. This bugs also occurred in Seq24 0.9.2. It occurs with the allofarow.mid file when doing Ctrl-A Ctrl-C Ctrl-V Move-Mouse Left-Click. It turns out the original code was checking only the first event to see if it was a Note event. For sequences that started with a Control Change or Program Change (or other non-Note events), the highest note was never modified, and none of the note events were adjusted.

Finally, we only want to transpose note events (i.e. alter m_data[0]), and not other kinds of events. We still need to figure out what to do with aftertouch, though. Currently likely to be covered by the processing of the note that it accompanies.

Threadsafe

Parameters

tick	The time destination for the paste. This represents the "x" coordinate of the upper left corner of the paste-box. It will be converted to an offset, for example pasting every event 48 ticks forward from the original copy.	
note	The note/pitch destination for the paste. This represents the "y" coordinate of the upper left corner of the paste-box. It will be converted to an offset, for example pasting every event 7 notes higher than the original copy.	

12.67.5.131 get_selected_box()

```
int & note_h,
midipulse & tick_f,
int & note_l )
```

Note the common-code betweem this function and <code>get_clipboard_box()</code>. Also note we could return a boolean indicating if the return values were filled in.

Threadsafe

Parameters

out	tick_s	Side-effect return reference for the start time.
out	note⊷	Side-effect return reference for the high note.
	_h	
out	tick_f	Side-effect return reference for the finish time.
out	note⊷	Side-effect return reference for the low note.
	1	

12.67.5.132 get_clipboard_box()

Note the common-code betweem this function and get_selected_box(). Also note we could return a boolean indicating if the return values were filled in.

Threadsafe

Parameters

out	tick_s	Side-effect return reference for the start time.
out	note⊷	Side-effect return reference for the high note.
	_h	
out	tick_f	Side-effect return reference for the finish time.
out	note⊷	Side-effect return reference for the low note.
	_/	

12.67.5.133 adjust_timestamp()

- If the timestamp plus the delta is greater that m_length, we do round robin magic.
- If the timestamp is greater than m_length, then it is wrapped around to the beginning.
- If the timestamp equals m_length, then it is set to 0, and later, trimmed.

• If the timestamp is less than 0, then it is set to the end.

Taken from similar code in move_selected_notes() and grow_selected(). Be careful using this function.

Parameters

t	Provides the timestamp to be adjusted based on m_length.	
isnoteoff	Used for "expanding" the timestamp from 0 to just less than m_length, if necessary. Should be set to true only for Note Off events; it defaults to false, which means to wrap the events around the end of the sequence if necessary, and is used only in movement, not in growth.	

Returns

Returns the adjusted timestamp.

12.67.5.134 trim_timestamp()

Similar to adjust_timestamp, but it doesn't have an isnoteoff parameter.

Parameters

t Provides the timestamp to be adjusted based on m_length.

Returns

Returns the adjusted timestamp.

12.67.5.135 clip_timestamp()

If the new (off) timestamp is less than the on-time, it is clipped to the snap value. If it is greater than the length of the sequence, then it is clipped to the sequence length. No wrap-around.

Parameters

ontime	Provides the original time, which limits the amount of negative adjustment that can be done.
offtime	Provides the timestamp to be adjusted and clipped.

Returns

Returns the adjusted timestamp.

12.67.5.136 move_selected_notes()

Also currently moves any other events in the range of the selection.

Also, we've moved external calls to push_undo() into this function. The caller shouldn't have to do that.

Another thing this function does is wrap-around when movement occurs. Any events (except Note Off) that will start just after the END of the pattern will be wrapped around to the beginning of the pattern.

Fixed:

Select all notes in a short pattern that starts at time 0 and has non-note events starting at time 0 (see contrib/midi/allofarow.mid); move them with the right arrow, and move them back with the left arrow; then view in the event editor, and see that the non-Note events have not moved back, and in fact move way too far to the right, actually to near the END marker. We've fixed that in the new adjust_timestamp() function.

This function checks for any marked events in seq24, but now we make sure the event is a Note On or Note Off event before dealing with it. We now handle properly events like Program Change, Control Change, and Pitch Wheel. Remember that Aftertouch is treated like a note, as it has velocity. For non-Notes, event::get_note() returns m_data[0], and we don't want to adjust that.

Note

We leave a small gap where mark_selected() locks and unlocks, then we lock again. This should only be an issue if moving notes while the sequence is playing.

Parameters

delta_tick	Provides the amount of time to move the selected notes. Note that it also applies to events. Note-Off events are expanded to m_length if their timestamp would be 0. All other events will wrap around to 0.
delta_note	Provides the amount of pitch to move the selected notes. This value is applied only to Note (On and Off) events. Also, if this value would bring a note outside the range of 0 to 127, that note is not changed and the event is not moved.

12.67.5.137 add_note()

It adds a single note-on / note-off pair.

The paint parameter indicates if we care about the painted event, so then the function runs though the events and deletes the painted ones that overlap the ones we want to add.

Also note that push_undo() is not incorporated into this function, for the sake of speed.

Here, we could ignore events not on the sequence's channel, as an option. We have to be careful because this function can be used in painting notes.

Stazed:

```
http://www.blitter.com/~russtopia/MIDI/~jglatt/tech/midispec.htm

Note Off: The first data is the note number. There are 128 possible notes on a MIDI device, numbered 0 to 127 (where Middle C is note number 60). This indicates which note should be released. The second data byte is the velocity, a value from 0 to 127. This indicates how quickly the note should be released (where 127 is the fastest). It's up to a MIDI device how it uses velocity information. Often velocity
```

will be used to tailor the VCA release time. MIDI devices that can

generate Note Off messages, but don't implement velocity features, will transmit Note Off messages with a preset velocity of 64.

Also, we now see that seq24 never used the recording-velocity member (m_rec_vol). We use it to modify the new m_note_on_velocity member if the user changes it in the seqedit window.

Threadsafe

Parameters

tick	The time destination of the new note, in pulses.	
len The duration of the new note, in pulses.		
note	The pitch destination of the new note.	
paint	If true, repaint the whole set of events, in order to be left with a clean view of the inserted event. The	
	default is false.	

12.67.5.138 add_chord()

If SEQ64_STAZED_CHORD_GENERATOR is not defined, it devolves to add_note().

Threadsafe

Parameters

tick	The time destination of the new note, in pulses.
len	The duration of the new note, in pulses.
note	The pitch destination of the new note.
paint	If true, repaint to be left with just the inserted event.

```
midibyte status,
midibyte d0,
midibyte d1,
bool paint = false )
```

The paint parameter indicates if we care about the painted event, so then the function runs though the events and deletes the painted ones that overlap the ones we want to add.

Threadsafe

Parameters

tick	The time destination of the event.
status	The type of event to add.
d0	The first data byte for the event.
d1	The second data byte for the event (if needed).
paint	If true, the inserted event is marked for painting.

12.67.5.140 stream_event()

```
bool seq64::sequence::stream_event ( event \& ev )
```

The event's timestamp is adjusted, if needed. If recording:

```
If the pattern is playing, the event is added.
If the pattern is playing and quantized record is in force, the note's timestamp is altered.
If not playing, but the event is a Note On or Note Off, we add it and keep track of it.
```

If MIDI Thru is enabled, the event is put on the buss.

We are adding a feature where events are rejected if their channel doesn't match that of the sequence. This has been a complaint of some people. Could modify the add_event() and add_note() functions, but better to do it here for comprehensive event support. Also have to make sure the event-channel is preserved before this function is called, and also need to make sure that the channel is appended on both playback and in saving of the MIDI file.

We are also adding the usage, at last, of the m_rec_vol member.

Todo When we feel like debugging, we will replace the global is-playing call with the parent perform's is-running call.

Threadsafe

Parameters

Returns

Returns true if the event's channel matched that of this sequence, and the channel-matching feature was set to true. Also returns true if we're not using channel-matching. A return value of true means the event should be saved.

12.67.5.141 change_event_data_range()

Changes only selected events, if any.

Threadsafe

Let t == the current tick value; t == tick start value; t == tick finish value; t == tic

If this were an interpolation formula it would be:

$$d = ds + (df - ds) - - - ts$$

Something is not quite right; to be investigated.

Parameters

tick⊷	Provides the starting tick value.
_s	
tick⊷	Provides the ending tick value.
_f	
status	Provides the event status that is to be changed.
СС	Provides the event control value.
data⊷	Provides the starting data value.
_s	
data⊷	Provides the finishing data value.
_f	

Returns

Returns true if the data was changed.

12.67.5.142 change_event_data_lfo()

12.67.5.143 increment_selected()

The supported statuses are:

```
- EVENT_NOTE_ON
- EVENT_NOTE_OFF
- EVENT_AFTERTOUCH
- EVENT_CONTROL_CHANGE
- EVENT_PITCH_WHEEL
```

- EVENT_PROGRAM_CHANGE

- EVENT_CHANNEL_PRESSURE

Threadsafe

Parameters

```
astat The desired event.
```

Parameter "acontrol", the desired control-change, is unused. This might be a bug, or at least a missing feature.

12.67.5.144 decrement_selected()

The supported statuses are:

- · One-byte messages
 - EVENT PROGRAM CHANGE
 - EVENT_CHANNEL_PRESSURE
- · Two-byte messages
 - EVENT_NOTE_ON
 - EVENT_NOTE_OFF

- EVENT_AFTERTOUCH
- EVENT_CONTROL_CHANGE
- EVENT_PITCH_WHEEL

astat	The desired event.
-------	--------------------

Parameter "acontrol", the desired control-change, is unused. This might be a bug, or at least a missing feature.

12.67.5.145 grow_selected()

And, though it doesn't move Note Off events, it does reconstruct them.

This function is called when doing a ctrl-left mouse move on the selected notes or when using ctrl-left-arrow or ctrl-right-arrow to shrink or stretch the selected notes. Using the mouse allows pretty much any amount of growth or shrinkage, but use the arrow keys limits the changes to the current snap value.

This function grows/shrinks only Note On events that are marked and linked. If an event is not linked, this function now ignores the event's timestamp, rather than risk a segfault on a null pointer. Compare this function to the stretch selected() and move selected notes() functions.

This function would strip out non-Notes, but now it at least preserves them and moves them, to try to preserve their relative position re the notes.

In any case, we want to mark the original off-event for deletion, otherwise we get duplicate off events, for example in the "Begin/End" pattern in the test.midi file.

This function now tries to prevent pathological growth, such as trying to shrink the notes to zero length or less, or stretch them beyond the length of the sequence. Otherwise we get weird and unexpected results. Also, we've moved external calls to push_undo() into this function. The caller shouldn't have to do that.

A comment on terminology: The user "selects" notes, while the sequencer "marks" notes. The first thing this function does is mark all the selected notes.

Threadsafe

Parameters

delta An offset for each linked event's timestamp.

12.67.5.146 stretch_selected()

This should move a note off event, according to old comments, but it doesn't seem to do that. See the grow_ selected() function. Rather, it moves any event in the selection.

Also, we've moved external calls to push_undo() into this function. The caller shouldn't have to do that.

delta_tick	Provides the amount of time to stretch the selected notes.	
------------	--	--

```
12.67.5.147 remove_marked()
```

```
bool seq64::sequence::remove_marked ( )
```

Note how this function forwards the call to m_event.remove_marked().

Threadsafe

Returns

Returns true if at least one event was removed.

12.67.5.148 mark_selected()

```
bool seq64::sequence::mark_selected ( )
```

Threadsafe

Returns

Returns true if there were any events that got marked.

12.67.5.149 remove_selected()

```
void seq64::sequence::remove_selected ( )
```

This is a new convenience function to fold in the push_undo() and mark_selected() calls. It makes the process slightly faster, as well.

Threadsafe Also makes the whole process threadsafe.

12.67.5.150 unpaint_all()

```
void seq64::sequence::unpaint_all ( )
```

Threadsafe

12.67.5.151 unselect()

```
void seq64::sequence::unselect ( )
```

```
12.67.5.152 verify_and_link()

void seq64::sequence::verify_and_link ( )

Threadsafe

12.67.5.153 link_new()

void seq64::sequence::link_new ( )

Threadsafe

12.67.5.154 zero_markers()

void seq64::sequence::zero_markers ( ) [inline]
```

This function is used when the sequencer stops. This function currently sets m_last_tick = 0, but we would like to avoid that if doing a pause, rather than a stop, of playback. However, commenting out this setting doesn't have any effect that we can see with a quick look at the user-interface.

It flushes a note to the midibus to preview its sound, used by the virtual piano.

Threadsafe

Parameters

note The note to play. It is not checked for range validity, for the sake of speed.

```
12.67.5.156 play_note_off()

void seq64::sequence::play_note_off (
    int note )
```

Threadsafe

Parameters

note The note to turn off. It is not checked for range validity, for the sake of speed.

12.67.5.157 off_playing_notes()

```
void seq64::sequence::off_playing_notes ( )
```

This function does not bother checking if m_masterbus is a null pointer.

Threadsafe

```
12.67.5.158 pause()

void seq64::sequence::pause ( )
```

The reset() function is currently not called when pausing, but we still need the note-shutoff capability to prevent notes from lingering. Note that we do not call set_playing(false)... it disarms the sequence, which we do not want upon pausing.

Note that, in live mode, the user controls playback, while otherwise JACK or the performance/song editor controls playback. (We're still a bit confounded about these modes, alas.)

Parameters

song_mode True if song mode is on. This can mean that JACK transport is not in control of playback.

```
12.67.5.160 reset_draw_marker()
void seq64::sequence::reset_draw_marker ( )
```

It resets the draw marker so that calls to get_next_note_event() will start from the first event.

Threadsafe

When it has no more events, returns a false.

out	tick_s	Provides a pointer destination for the start time.
out	tick_f	Provides a pointer destination for the finish time.
out	note	Provides a pointer destination for the note pitch value Probably should be a midibyte value.
out	selected	Provides a pointer destination for the selection status of the note.
out	velocity	Provides a pointer destination for the note velocity. Probably should be a midibyte value.

12.67.5.163 get_minmax_note_events()

Todo For efficency, we should calculate this only when the event set changes, and save the results and return them if good.

Threadsafe

Parameters

lowest	A reference parameter to return the note with the lowest value. if there are no notes, then it is set to SEQ64_MIDI_COUNT_MAX-1.
highest	A reference parameter to return the note with the highest value. if there are no notes, then it is set to -1.

Returns

If there are no notes in the list, then false is returned, and the results should be disregarded.

12.67.5.164 get_next_event() [1/2]

```
bool seq64::sequence::get_next_event (
    midibyte status,
    midibyte cc,
    midipulse * tick,
    midibyte * d0,
    midibyte * d1,
    bool * selected,
    int evtype = EVENTS_ALL )
```

Then set the rest of the parameters parameters using that event. If the status is the new value EVENT_ANY, then any event will be obtained.

Note the usage of event::is_desired_cc_or_not_cc(status, cc, *d0); Either we have a control change with the right CC or it's a different type of event.

status	The type of event to be obtained. The special value EVENT_ANY can be provided so that no event
	statuses are filtered.
СС	The continuous controller value that might be desired.
tick	A pointer return value for the tick value of the next event found.
d0	A pointer return value for the first data value of the event.
d1	A pointer return value for the second data value of the event.
selected	A pointer return value for the is-selected status of the event.
evtype	A stazed parameter for picking either all event or unselected events.

Then set the status and control character parameters using that event.

Parameters

status	Provides a pointer to the MIDI status byte to be set, as a way to retrieve the event.
СС	The return pointer for the control value.

12.67.5.166 get_next_trigger()

12.67.5.167 quantize_events()

One confusing things is why the original versions of the events don't seem to be deleted.

Parameters

status	Indicates the type of event to be quantized.
СС	The desired control-change to count, if the event is a control-change.
snap_tick	Provides the maximum amount to move the events. Actually, events are moved to the previous or next snap_tick value depend on whether they are halfway to the next one or not.
divide	A rough indicator of the amount of quantization. The only values used in the application seem to Generated by Doxygen be either 1 or 2.
linked	False by default, this parameter indicates if marked events are to be relinked, as far as we can tell.

12.67.5.168 push_quantize()

If the scale value is 0, this is "no scale", which is the chromatic scale, where all 12 notes, including sharps and flats, are part of the scale.

Also, we've moved external calls to push_undo() into this function. The caller shouldn't have to do that.

Note

We noticed (ca 2016-06-10) that MIDI aftertouch events need to be transposed, but are not being transposed here. Assuming they are selectable (another question!), the test for note-on and note-off is not sufficient, and so has been replaced by a call to event::is_note_msg().

Parameters

steps	The number of steps to transpose the notes.
scale	The scale to make the notes adhere to while transposing.

12.67.5.170 shift_notes()

12.67.5.171 multiply_pattern()

midibyte seq64::sequence::musical_key () const [inline]

```
12.67.5.173 musical_key() [2/2]
void seq64::sequence::musical_key (
             int key ) [inline]
12.67.5.174 musical_scale() [1/2]
midibyte seq64::sequence::musical_scale ( ) const [inline]
12.67.5.175 musical_scale() [2/2]
void seq64::sequence::musical_scale (
             int scale ) [inline]
12.67.5.176 background_sequence() [1/2]
int seq64::sequence::background_sequence ( ) const [inline]
12.67.5.177 background_sequence() [2/2]
void seq64::sequence::background_sequence (
             int bs ) [inline]
Disabling the sequence number (setting it to SEQ64_SEQUENCE_LIMIT) is valid.
12.67.5.178 show_events()
void seq64::sequence::show_events ( ) const
12.67.5.179 copy_events()
void seq64::sequence::copy_events (
             const event_list & newevents )
```

Compare this function to the remove_all() function. Copying the container is a lot of work, but fairly fast, even with an std::multimap as the container.

Threadsafe Note that we had to consolidate the replacement of all the events in the container in order to prevent the "Save to Sequence" button in the eventedit object from causing the application to segfault. It would segfault when the mainwnd timer callback would fire, causing updates to the sequence's slot pixmap, which would then try to access deleted events. Part of the issue was that note links were dropped when copying the events, so now we call verify_and_link() to hopefully reconstitute the links.

ſ	newevents	Provides the container of MIDI events that will completely replace the current container. Normally	
		this container is supplied by the event editor, via the eventslots class.	

Makes if-clauses easier to read.

Parameters

е	Provides the event to be checked.
status	Provides the event type that must be matched.
tick←	The lower end of the range of timestamps that the event must fall within.
_s	
tick←	The upper end of the range of timestamps that the event must fall within.
_f	

midipulse tick_f) const [inline], [private]

Returns

Returns true if the event matchs all of the restrictions noted.

12.67.5.182 set_parent()

Remember that m_parent is not at all owned by the sequence. We just don't want to do all the work necessary to make it a reference, at this time.

Parameters

p A pointer to the parent, assigned only if not already assigned.

12.67.5.183 put_event_on_bus()

```
void seq64::sequence::put\_event\_on\_bus (
```

```
event & ev ) [private]
```

This function does not bother checking if m_masterbus is a null pointer.

Parameters

```
ev The event to put on the buss.
```

Threadsafe

12.67.5.184 set_trigger_offset()

If m_length is 0, then m_trigger_offset is simply set to the parameter.

Threadsafe

Parameters

trigger_offset	The full trigger offset to set.
----------------	---------------------------------

12.67.5.185 adjust_trigger_offsets_to_length()

Threadsafe

Might can get rid of this function?

Parameters

The new length of the adjusted trigger.	newlength
---	-----------

12.67.5.186 adjust_offset()

We no longer bother checking the pointer. If it is bad, all hope is lost. If the event is a note off, and that note is currently playing, then send a note off.

Not threadsafe

i Provides the iterator to the event to remove from the event list.

Finds the given event in m_events, and removes the first iterator matching that. If there are events that would match after that, they remain in the container. This matches seq24 behavior.

Not threadsafe

Parameters

e Provides a reference to the event to be removed.

```
12.67.5.189 remove_all()
void seq64::sequence::remove_all ( ) [private]
```

Unsets the modified flag. (Why?) Also see the new copy_events() function.

12.67.5.190 channel_match()

Parameters

e The event whose channel nybble is to be checked.

Returns

Returns true if the channel-matching feature is enable and the channels match, or true if the channel-matching feature is turned off.

12.67.6 Friends And Related Function Documentation

12.67.6.1 perform

```
friend class perform [friend]
```

12.67.6.2 triggers

friend class triggers [friend]

12.67.7 Field Documentation

```
12.67.7.1 m events clipboard
```

```
event_list seq64::sequence::m_events_clipboard [static], [private]
```

Being static allows for copy/paste between patterns.

```
12.67.7.2 m_parent
```

```
perform* seq64::sequence::m_parent [private]
```

We can use the rc_settings flag(s), but JACK could be disconnected. We could use a reference here, but, to avoid modifying the midifile class as well, we use a pointer. It is set in perform::add_sequence(). This member would also be using for passing modification status to the parent, so that the GUI code doesn't have to do it.

```
12.67.7.3 m_events
```

```
event_list seq64::sequence::m_events [private]
```

It used to be called m_list_events, but a map implementation is now available, and is the default.

```
12.67.7.4 m_triggers
```

```
triggers seq64::sequence::m_triggers [private]
```

12.67.7.5 m_events_undo_hold

```
event_list seq64::sequence::m_events_undo_hold [private]
```

Changed, of course, from std::list<event> to the sequence::Events typedef.

```
Events m_events_undo_hold;
```

12.67.7.6 m_have_undo

```
bool seq64::sequence::m_have_undo [private]
```

12.67.7.7 m_have_redo

```
bool seq64::sequence::m_have_redo [private]
```

Previously, unlike the perfedit, the seqedit did not provide a redo facility.

```
12.67.7.8 m_events_undo
EventStack seq64::sequence::m_events_undo [private]
12.67.7.9 m_events_redo
EventStack seq64::sequence::m_events_redo [private]
12.67.7.10 m_iterator_draw
event_list::iterator seq64::sequence::m_iterator_draw [private]
12.67.7.11 m_channel_match
bool seq64::sequence::m_channel_match [private]
If true (not yet the default), then the seqedit window will record only MIDI events that match its channel. The old
behavior is preserved if this variable is set to false.
12.67.7.12 m_midi_channel
midibyte seq64::sequence::m_midi_channel [private]
However, if this value is EVENT_NULL_CHANNEL (0xFF), then this sequence is an SMF 0 track, and has no single
channel.
12.67.7.13 m_bus
midibyte seq64::sequence::m_bus [private]
12.67.7.14 m_song_mute
bool seq64::sequence::m_song_mute [private]
12.67.7.15 m_transposable
bool seq64::sequence::m_transposable [private]
A potential feature from stazed's seq32 project. Now it is an actual, configurable feature.
12.67.7.16 m_notes_on
int seq64::sequence::m_notes_on [private]
```

Provides the main dirtiness flag.

```
12.67.7.17 m_masterbus
mastermidibus* seq64::sequence::m_masterbus [private]
12.67.7.18 m_playing_notes
int seq64::sequence::m_playing_notes[SEQ64_MIDI_NOTES_MAX] [private]
It is used when muting, to shut off the notes that are playing.
12.67.7.19 m_was_playing
bool seq64::sequence::m_was_playing [private]
12.67.7.20 m_playing
bool seq64::sequence::m_playing [private]
12.67.7.21 m_recording
bool seq64::sequence::m_recording [private]
12.67.7.22 m_quantized_rec
bool seq64::sequence::m_quantized_rec [private]
12.67.7.23 m_thru
bool seq64::sequence::m_thru [private]
12.67.7.24 m_queued
bool seq64::sequence::m_queued [private]
12.67.7.25 m_dirty_main
bool seq64::sequence::m_dirty_main [private]
```

```
12.67.7.26 m_dirty_edit
bool seq64::sequence::m_dirty_edit [private]
12.67.7.27 m_dirty_perf
bool seq64::sequence::m_dirty_perf [private]
12.67.7.28 m_dirty_names
bool seq64::sequence::m_dirty_names [private]
12.67.7.29 m_editing
bool seq64::sequence::m_editing [private]
12.67.7.30 m_raise
bool seq64::sequence::m_raise [private]
It allows a sequence editor window to pop up if not already raised, in seqedit::timeout().
12.67.7.31 m_name
std::string seq64::sequence::m_name [private]
12.67.7.32 m_last_tick
midipulse seq64::sequence::m_last_tick [private]
Provides the last tick played.
12.67.7.33 m_queued_tick
midipulse seq64::sequence::m_queued_tick [private]
12.67.7.34 m_trigger_offset
midipulse seq64::sequence::m_trigger_offset [private]
```

```
12.67.7.35 m_maxbeats
const int seq64::sequence::m_maxbeats [private]
Hardwired to c_maxbeats at present.
12.67.7.36 m_ppqn
int seq64::sequence::m_ppqn [private]
12.67.7.37 m_seq_number
int seq64::sequence::m_seq_number [private]
This number is set in the perform::install_sequence() function.
12.67.7.38 m_length
```

This value should be a power of two when used as a bar unit.

midipulse seq64::sequence::m_length [private]

```
12.67.7.39 m_snap_tick
midipulse seq64::sequence::m_snap_tick [private]
```

It starts out as the value m_ppqn / 4.

12.67.7.40 m_time_beats_per_measure

```
int seq64::sequence::m_time_beats_per_measure [private]
```

Defaults to 4. Used by the sequence editor to mark things in correct time on the user-interface.

```
12.67.7.41 m_time_beat_width
int seq64::sequence::m_time_beat_width [private]
```

Defaults to 4, which means the beat is a quarter note. A value of 8 would mean it is an eighth note. Used by the sequence editor to mark things in correct time on the user-interface.

```
12.67.7.42 m_clocks_per_metronome
int seq64::sequence::m_clocks_per_metronome [private]
```

This value provides the number of MIDI clocks between metronome clicks. The default value of this item is 24. It can also be read from some SMF 1 files, such as our hymne.mid example.

```
12.67.7.43 m_32nds_per_quarter
```

```
int seq64::sequence::m_32nds_per_quarter [private]
```

This value provides the number of notated 32nd notes in a MIDI quarter note (24 MIDI clocks). The usual (and default) value of this parameter is 8; some sequencers allow this to be changed.

```
12.67.7.44 m_us_per_quarter_note
```

```
long seq64::sequence::m_us_per_quarter_note [private]
```

This value can be extracted from the beats-per-minute value (mastermidibus::m_beats_per_minute), but here we set it to 0 by default, indicating that we don't want to write it. Otherwise, it can be read from a MIDI file, and saved here to be restored later.

```
12.67.7.45 m_rec_vol
```

```
int seq64::sequence::m_rec_vol [private]
```

12.67.7.46 m_note_on_velocity

```
int seq64::sequence::m_note_on_velocity [private]
```

Currently set to SEQ64_DEFAULT_NOTE_ON_VELOCITY. If the recording velocity (m_rec_vol) is non-zero, this value will be set to the desired recording velocity. A "stazed" feature.

```
12.67.7.47 m_note_off_velocity
```

```
int seq64::sequence::m_note_off_velocity [private]
```

Currently set to SEQ64_DEFAULT_NOTE_OFF_VELOCITY, and currently unmodifiable. A "stazed" feature.

```
12.67.7.48 m_musical_key
```

```
midibyte seq64::sequence::m_musical_key [private]
```

If the value is SEQ64_KEY_OF_C, then there is no musical key to be set.

```
12.67.7.49 m_musical_scale
```

```
midibyte seq64::sequence::m_musical_scale [private]
```

If the value is the enumeration value c_scale_off, then there is no musical scale to be set.

12.67.7.50 m_background_sequence

```
int seq64::sequence::m_background_sequence [private]
```

If the value is greater than max_sequence(), then there is no background sequence to be set.

```
12.67.7.51 m mutex
```

```
mutex seq64::sequence::m_mutex [mutable], [private]
```

Made mutable for use in certain locked getter functions.

```
12.67.7.52 m_note_off_margin
```

```
const midipulse seq64::sequence::m_note_off_margin [private]
```

Also used when the user attempts to shrink a note to zero (or less than zero) length.

12.68 seq64::trigger Class Reference

This class hold a single trigger for a sequence object.

Public Member Functions

• trigger ()

Initializes the trigger structure.

bool operator< (const trigger &rhs)

This operator compares only the m_tick_start members.

• midipulse length () const

'Getter' function for member m_tick_end and m_tick_start.

• midipulse tick_start () const

'Getter' function for member m_tick_start

void tick_start (midipulse s)

'Setter' function for member m tick start

void increment_tick_start (midipulse s)

'Setter' function for member m_tick_start

void decrement_tick_start (midipulse s)

'Setter' function for member m_tick_start

• midipulse tick_end () const

'Getter' function for member m_tick_end

• void tick_end (midipulse e)

'Setter' function for member m_tick_end

void increment_tick_end (midipulse s)

'Setter' function for member m_tick_end

· void decrement tick end (midipulse s)

'Setter' function for member m_tick_end

midipulse offset () const

'Getter' function for member m_offset

• void offset (midipulse o)

'Setter' function for member m_offset

• void increment_offset (midipulse s)

'Setter' function for member m_offset

• void decrement_offset (midipulse s)

'Setter' function for member m_offset

• bool selected () const

'Getter' function for member m_selected

void selected (bool s)

'Setter' function for member m_selected

Private Attributes

• midipulse m_tick_start

Provides the starting tick for this trigger.

• midipulse m_tick_end

Provides the ending tick for this trigger.

· midipulse m_offset

Provides the offset for this trigger.

· bool m selected

Indicates that the trigger is part of a selection.

12.68.1 Detailed Description

This class is used in playback, and is contained in the triggers class.

12.68.2 Constructor & Destructor Documentation

```
12.68.2.1 trigger()
```

```
seq64::trigger::trigger ( ) [inline]
```

12.68.3 Member Function Documentation

```
12.68.3.1 operator<()
```

Parameters

rhs The "right-hand side" of the less-than operation.

Returns

Returns true if m_tick_start is less than rhs's.

```
12.68.3.2 length()
midipulse seq64::trigger::length ( ) const [inline]
```

We've seen that some of the calculations of trigger length are wrong, being 1 tick less than the true length of the trigger in pulses. This function calculates trigger length the correct way.

```
12.68.3.3 tick_start() [1/2]
midipulse seq64::trigger::tick_start ( ) const [inline]
12.68.3.4 tick_start() [2/2]
void seq64::trigger::tick_start (
             midipulse s ) [inline]
12.68.3.5 increment_tick_start()
void seq64::trigger::increment_tick_start (
             midipulse s) [inline]
12.68.3.6 decrement_tick_start()
void seq64::trigger::decrement_tick_start (
             midipulse s ) [inline]
12.68.3.7 tick_end() [1/2]
midipulse seq64::trigger::tick_end ( ) const [inline]
12.68.3.8 tick_end() [2/2]
void seq64::trigger::tick_end (
             midipulse e ) [inline]
12.68.3.9 increment_tick_end()
void seq64::trigger::increment_tick_end (
             midipulse s ) [inline]
```

```
12.68.3.10 decrement_tick_end()
void seq64::trigger::decrement_tick_end (
             midipulse s ) [inline]
12.68.3.11 offset() [1/2]
midipulse seq64::trigger::offset ( ) const [inline]
12.68.3.12 offset() [2/2]
void seq64::trigger::offset (
             midipulse o ) [inline]
12.68.3.13 increment_offset()
void seq64::trigger::increment_offset (
             midipulse s ) [inline]
12.68.3.14 decrement_offset()
void seq64::trigger::decrement_offset (
             midipulse s ) [inline]
12.68.3.15 selected() [1/2]
bool seq64::trigger::selected ( ) const [inline]
12.68.3.16 selected() [2/2]
void seq64::trigger::selected (
            bool s ) [inline]
12.68.4 Field Documentation
12.68.4.1 m_tick_start
midipulse seq64::trigger::m_tick_start [private]
12.68.4.2 m_tick_end
midipulse seq64::trigger::m_tick_end [private]
```

12.68.4.3 m_offset

```
midipulse seq64::trigger::m_offset [private]

12.68.4.4 m_selected
```

12.69 seq64::triggers Class Reference

bool seq64::trigger::m_selected [private]

The triggers class is a receptable the triggers that can be used with a sequence object.

Public Member Functions

• triggers (sequence &parent)

Principal constructor.

• ∼triggers ()

A rote destructor.

• triggers & operator= (const triggers &rhs)

Principal assignment operator.

void set_ppqn (int ppqn)

'Setter' function for member m_ppqn We have to set this value after construction for best safety.

• void set_length (int len)

'Setter' function for member m_length We have to set this value after construction for best safety.

const List & triggerlist () const

'Getter' function for member m_triggers This is the const version

• List & triggerlist ()

'Getter' function for member m_triggers

void push_undo ()

Pushes the list-trigger into the trigger undo-list, then flags each item in the undo-list as unselected.

• void pop_undo ()

If the trigger undo-list has any items, the list-trigger is pushed into the redo list, the top of the undo-list is coped into the list-trigger, and then pops from the undo-list.

void pop redo ()

If the trigger redo-list has any items, the list-trigger is pushed into the undo list, the top of the redo-list is coped into the list-trigger, and then pops from the redo-list.

· void print (const std::string &seqname) const

Prints a list of the currently-held triggers.

bool play (midipulse &starttick, midipulse &endtick)

If playback-mode (song mode) is in force, that is, if using in-triggers and on/off triggers, this function handles that kind of playback.

• void add (midipulse tick, midipulse len, midipulse offset=0, bool adjustoffset=true)

Adds a trigger.

· void adjust_offsets_to_length (midipulse newlen)

Adjusts trigger offsets to the length specified for all triggers, and undo triggers.

· void split (midipulse tick)

Splits the first trigger that brackets the splittick parameter.

• void grow (midipulse tickfrom, midipulse tickto, midipulse length)

Grows a trigger.

void remove (midipulse tick)

Deletes the first trigger that brackets the given tick from the trigger-list.

bool get state (midipulse tick)

Checks the list of triggers against the given tick.

bool select (midipulse tick)

Checks the list of triggers against the given tick.

bool unselect ()

Unselects all triggers.

bool intersect (midipulse position, midipulse &start, midipulse &end)

This function examines each trigger in the trigger list.

void remove_selected ()

Deletes the first selected trigger that is found.

void copy_selected ()

Copies the first selected trigger that is found.

void paste (midipulse paste_tick=SEQ64_NO_PASTE_TRIGGER)

If there is a copied trigger, then this function grabs it from the trigger clipboard and adds it.

bool move_selected (midipulse tick, bool adjustoffset, grow_edit_t which=GROW_MOVE)

Moves selected triggers as per the given parameters.

• midipulse get_selected_start ()

Gets the selected trigger's start tick.

• midipulse get_selected_end ()

Gets the selected trigger's end tick.

midipulse get_maximum ()

Get the ending value of the last trigger in the trigger-list.

· void move (midipulse starttick, midipulse distance, bool direction)

Moves triggers in the trigger-list.

· void copy (midipulse starttick, midipulse distance)

Not sure what these diagrams are for yet.

• void clear ()

Clears the whole list of triggers.

bool next (midipulse *tick_on, midipulse *tick_off, bool *selected, midipulse *tick_offset)

Get the next trigger in the trigger list, and set the parameters based on that trigger.

trigger next_trigger ()

Get the next trigger in the trigger list.

void reset_draw_trigger_marker ()

Sets the draw-trigger iterator to the beginning of the trigger list.

- void set trigger paste tick (midipulse tick)
- · midipulse get_trigger_paste_tick () const

Private Types

```
    enum grow_edit_t {
        GROW_START,
        GROW_END,
        GROW MOVE }
```

Provides a typedef introduced by Stazed to make the trigger grow/move code easier to understand.

typedef std::list< trigger > List

Exposes the triggers type, currently needed for midi container only.

typedef std::stack< List > Stack

Provides a stack for use with the undo/redo features of the trigger support.

Private Member Functions

· midipulse adjust_offset (midipulse offset)

Adjusts the given offset by mod'ing it with m_length and adding m_length if needed, and returning the result.

void split (trigger &trig, midipulse splittick)

Splits the trigger given by the parameter into two triggers.

Private Attributes

· sequence & m_parent

Holds a reference to the parent sequence object that owns this trigger object.

· List m_triggers

This list holds the current pattern/triggers events.

· trigger m clipboard

This item holds a single copied trigger, to be pasted later.

· Stack m undo stack

Handles the undo list for a series of operations on triggers.

Stack m_redo_stack

Handles the redo list for a series of operations on triggers.

· List::iterator m iterator play trigger

An iterator for cycling through the triggers during playback.

• List::iterator m_iterator_draw_trigger

An iterator for cycling through the triggers during drawing.

• bool m_trigger_copied

Set to true if there is an active trigger in the trigger clipboard.

• midipulse m_paste_tick

The tick point for pasting.

int m_ppqn

Holds the value of the PPQN from the parent sequence, for easy access.

• int m_length

Holds the value of the length from the parent sequence, for easy access.

Friends

- · class midi container
- · class midifile
- class sequence
- class Seq24PerfInput
- class FruityPerfInput

12.69.1 Member Typedef Documentation

12.69.1.1 List

typedef std::list<trigger> seq64::triggers::List [private]

12.69.1.2 Stack

typedef std::stack<List> seq64::triggers::Stack [private]

12.69.2 Member Enumeration Documentation

12.69.2.1 grow_edit_t

enum seq64::triggers::grow_edit_t [private]

Enumerator

GROW_START	Grow the start of the trigger.
GROW_END	Grow the end of the trigger.
GROW_MOVE	Move the entire trigger block.

12.69.3 Constructor & Destructor Documentation

12.69.3.1 triggers()

Parameters

parent The triggers object often needs to tell its parent sequence object what to do (such as stop playing).

12.69.3.2 ∼triggers()

```
seq64::triggers::~triggers ( )
```

12.69.4 Member Function Documentation

12.69.4.1 operator=()

Follows the stock rules for such an operator, but does a little more then just assign member values.

FIXED, BEWARE: Currently, it does not assign them all, so we should create a partial_copy() function to do this work, and use it where it is needed.

Parameters

```
rhs Provides the "right-hand side" of the assignment operation.
```

Returns

Returns a reference to self, for use in concatenated assignment operations.

12.69.4.2 set_ppqn()

```
12.69.4.3 set_length()
```

Also, there a chance that the length of the parent might change from time to time. Currently, only the sequence constructor and midifile call this function.

```
12.69.4.4 triggerlist() [1/2]
const List& seq64::triggers::triggerlist ( ) const [inline]
12.69.4.5 triggerlist() [2/2]
List& seq64::triggers::triggerlist ( ) [inline]
12.69.4.6 push_undo()
void seq64::triggers::push_undo ( )
12.69.4.7 pop_undo()
void seq64::triggers::pop_undo ( )
12.69.4.8 pop_redo()
void seq64::triggers::pop_redo ( )
12.69.4.9 print()
void seq64::triggers::print (
             const std::string & seqname ) const
Parameters
 segname
            A tag name to accompany the print-out, for the human to read.
```

12.69.4.10 play()

This is a new function for sequence::play() to call.

The for-loop goes through all the triggers, determining if there is are trigger start/end values before the *end_tick*. If so, then the trigger state is set to true (start only within the tick range) or false (end is within the tick range), and the trigger tick is set to start or end. The first start or end trigger that is past the end tick cause the search to end.

If the trigger state has changed, then the start/end ticks are passed back to the sequence, and the trigger offset is adjusted.

Parameters

start_tick	Provides the starting tick value, and returns the modified value as a side-effect.
end_tick	Provides the ending tick value, and returns the modified value as a side-effect.

Returns

Returns true if we're through playing the frame (trigger turning off), and the caller should stop the playback.

12.69.4.11 add()

What is this?

Parameters

tick	Provides the tick (pulse) time at which the trigger goes on.
len	Provides the length of the trigger. This value is actually calculated from the "on" value minus the "off" value read from the MIDI file.
offset	This value specifies the offset of the trigger. It is a feature of the c_triggers_new that c_triggers doesn't have. It is the third value in the trigger specification of the Sequencer64 MIDI file.
fixoffset	If true, the offset parameter is modified by adjust_offset() first. We think that basically makes sure it is positive.

12.69.4.12 adjust_offsets_to_length()

Parameters

newlength	Provides the length to which to adjust the offsets.
-----------	---

COMMON CODE?

This is the first trigger where splittick is greater than L and less than R.

Parameters

splittick	Provides the tick that must be bracketed for the split to be made.
-----------	--

12.69.4.14 grow()

This function looks for the first trigger where the tickfrom parameter is between the trigger's tick-start and tick-end values. If found then the trigger's start is moved back to tickto, if necessary, or the trigger's end is moved to tickto plus the length parameter, if necessary.

Then this new trigger is added, and the function breaks from the search loop.

Parameters

tickfrom	The desired from-value back which to expand the trigger, if necessary.
tickto	The desired to-value towards which to expand the trigger, if necessary.
len	The additional length to append to tickto for the check.

12.69.4.15 remove()

tick Provides the tick to be examined.

12.69.4.16 get_state()

If any trigger is found to bracket that tick, then true is returned.

Parameters

tick Provides the tick of interest.

Returns

Returns true if a trigger is found that brackets the given tick.

12.69.4.17 select()

If any trigger is found to bracket that tick, then true is returned, and the trigger is marked as selected.

Parameters

tick Provides the tick of interest.

Returns

Returns true if a trigger is found that brackets the given tick.

12.69.4.18 unselect()

```
bool seq64::triggers::unselect ( )
```

Returns

Always returns false.

12.69.4.19 intersect()

If the given position is between the current trigger's tick-start and tick-end values, the these values are copied to the start and end parameters, respectively, and then we exit.

position	The position to examine.
start	The destination for the starting tick (m_tick_start) of the matching trigger.
ender	The destination for the ending tick (m_tick_end) of the matching trigger.

Returns

Returns true if a trigger was found whose start/end ticks contained the position. Otherwise, false is returned, and the start and end return parameters should not be used.

It pastes at the copy end. or at the paste-tick, if supplied.

Parameters

paste_tick	Provides the optional tick at which to paste the trigger. If not set to
	SEQ64_NO_PASTE_TRIGGER, this value is used to adjust the paste offset.

12.69.4.23 move_selected()

tick	The tick at which the trigger starts.
fixoffset	Set to true if the offset is to be adjusted.
which	Selects which movement will be done, as discussed above. See the values of the
	trigger::grow_edit_t type.

Returns

Returns true if there was room to move. Otherwise, false is returned. We need this feature to support keystoke movement of a selected trigger in the perfroll window, and keep it from continually incrementing when there can be no more movement. This causes moving the other direction to be delayed while the accumulating movement counter is used up. However, right now we can't rely on this result, and ignore it. There may be no way around this minor issue.

```
12.69.4.24 get_selected_start()
midipulse seq64::triggers::get_selected_start ( )
```

We guess this ends up selecting only one trigger, otherwise only the last selected one would effectively set the result.

Returns

Returns the tick_start() value of the last-selected trigger. If no triggers are selected, then midipulse(-1) is returned.

```
12.69.4.25 get_selected_end()
midipulse seq64::triggers::get_selected_end ( )
```

Returns

Returns the tick_end() value of the last-selected trigger. If no triggers are selected, then midipulse(-1) is returned.

```
12.69.4.26 get_maximum()
midipulse seq64::triggers::get_maximum ( )
```

Returns

Returns the tick-end for the last trigger, if available. Otherwise, 0 is returned.

12.69.4.27 move()

There's no way to optimize this by saving tick values, as they are potentially modified at each step.

	starttick	The current location of the triggers.
	distance	The distance away from the current location to which to move the triggers.
ĺ	direction	If true, the triggers are moved forward. If false, the triggers are moved backward.

12.69.4.28 copy()

```
void seq64::triggers::copy (
        midipulse starttick,
         midipulse distance )
... a
[ ][ ]
. . .
... a
. . .
  7 play
5
3
      offset
  10 play
L
     ] [ ] [] orig
[
[
     [ ] [ ][] split on the R marker, shift first [ ]
     delete middle
     move ticks
     L
          R
         ][ ] [] split on L
          ] [ ] [] increase all after L ]
0123456789abcdef0123456789abcdef
][ ][ ][ ][ ][ ]
      [ ][
                      ][]
          ] [
                                 ]
 ][ ][][][][][][
c 4 0 f c a 8
4 c 0 1 4 6 8
[ ][
                      e a
2 6 inverse offset
][][][][][][]]
                     ] [ ][ ]
 gfca8
4 c
        c ghkmn
                      inverse offset
0123456789abcdefghijklmonpq
ponmlkjihqfedcba9876543210
Ofedcba9876543210fedcba9876543210fedcba9876543210fedcba9876543210
```

Copies triggers to a point distant from a given tick.

starttick	The current location of the triggers.
distance	The distance away from the current location to which to copy the triggers.

Todo It would be a bit simpler to simply return a trigger object, wouldn't it?

Parameters

tick_on	Return value for the retrieval of the starting tick for the trigger.
tick_off	Return value for the retrieval of the ending tick for the trigger.
selected	Return value for the retrieval of the is-selected flag for the trigger.
offset	Return value for the retrieval of the offset for the trigger.

Returns

Returns true if a trigger was found. If false, the caller cannot rely on the values returned through the return parameters.

Side-effect(s) The value of the m_iterator_draw_trigger member will be altered by this call, unless pointing to the end of the triggerlist, or if there are no triggers.

```
12.69.4.31 next_trigger()

trigger seq64::triggers::next_trigger ( )
```

Returns

Returns the next trigger. If there is none, a default trigger object is returned.

```
12.69.4.32 reset_draw_trigger_marker()
void seq64::triggers::reset_draw_trigger_marker ( ) [inline]
```

```
12.69.4.33 set_trigger_paste_tick()
```

Returns

Returns the new offset. However, if m length is 0, no change is made, and the original offset is returned.

The original trigger ends 1 tick before the splittick parameter, and the new trigger starts at splittick and ends where the original trigger ended.

Parameters

trig	Provides the original trigger, and also holds the changes made to that trigger as it is shortened, as a side-effect.
splittick	The position just after where the original trigger will be truncated, and the new trigger begins.

12.69.5 Friends And Related Function Documentation

```
12.69.5.1 midi_container
friend class midi_container [friend]
12.69.5.2 midifile
friend class midifile [friend]
```

```
12.69.5.3 sequence
friend class sequence [friend]
12.69.5.4 Seq24PerfInput
friend class Seq24PerfInput [friend]
12.69.5.5 FruityPerfInput
friend class FruityPerfInput [friend]
12.69.6 Field Documentation
12.69.6.1 m_parent
sequence& seq64::triggers::m_parent [private]
12.69.6.2 m_triggers
List seq64::triggers::m_triggers [private]
12.69.6.3 m_clipboard
trigger seq64::triggers::m_clipboard [private]
12.69.6.4 m_undo_stack
Stack seq64::triggers::m_undo_stack [private]
12.69.6.5 m_redo_stack
Stack seq64::triggers::m_redo_stack [private]
12.69.6.6 m_iterator_play_trigger
List::iterator seq64::triggers::m_iterator_play_trigger [private]
12.69.6.7 m_iterator_draw_trigger
List::iterator seq64::triggers::m_iterator_draw_trigger [private]
```

```
12.69.6.8 m_trigger_copied
```

```
bool seq64::triggers::m_trigger_copied [private]
```

12.69.6.9 m_paste_tick

```
midipulse seq64::triggers::m_paste_tick [private]
```

Set to -1 if not in force. This is a new feature from stazed's Seq32 project.

12.69.6.10 m_ppqn

```
int seq64::triggers::m_ppqn [private]
```

This should not change, but we have to set it after construction, and so we provide a setter for it, set_ppqn(), called by the sequence constructor.

12.69.6.11 m_length

```
int seq64::triggers::m_length [private]
```

This might change, we're not yet sure.

12.70 seq64::user_instrument Class Reference

Provides data about the MIDI instruments, readable from the "user" configuration file.

Public Member Functions

user_instrument (const std::string &name="")

Default constructor.

• user_instrument (const user_instrument &rhs)

Copy constructor.

user instrument & operator= (const user instrument &rhs)

Principal assignment operator.

• bool is_valid () const

'Getter' function for member m_is_valid

• void set_defaults ()

Sets the default values.

• const std::string & name () const

'Getter' function for member m_instrument_def.instrument (name of instrument)

• int controller_count () const

'Getter' function for member m_controller_count This function returns the number of active controllers.

int controller_max () const

'Getter' function for member MIDI_CONTROLLER_MAX This function returns the maximum number of controllers, active or inactive.

const std::string & controller_name (int c) const

'Getter' function for member m_instrument_def.controllers[c]

bool controller_active (int c) const

'Getter' function for member m_instrument_def.controllers_active[c]

void set_controller (int c, const std::string &cname, bool isactive)

'Setter' function for member m_instrument_def.controllers[c] and .controllers_active[c] Only sets the controller values if the object is already valid.

Private Member Functions

• void set_name (const std::string &instname)

'Setter' function for member m_instrument_def.instrument If the name parameter is not empty, the validity flag is set to true, otherwise it is set to false.

void copy_definitions (const user_instrument &rhs)

Copies the array members from one instance of user_instrument to this one.

Private Attributes

• bool m_is_valid

Provides a validity flag, useful in returning a reference to a bogus object for internal error-check.

• int m_controller_count

Provides the actual number of non-default controllers actually set.

user_instrument_t m_instrument_def

The instance of the structure that this class wraps.

12.70.1 Detailed Description

Will later make the size adjustable, if it makes sense to do so.

12.70.2 Constructor & Destructor Documentation

Fills in the defaults for the instrument definition, sets its name, and provides some light validation.

Parameters

name The name of the instrument, valid only if it is not empty.

```
12.70.2.2 user_instrument() [2/2]
```

Parameters

rhs The sources of the data for the copy.

12.70.3 Member Function Documentation

```
12.70.3.1 operator=()
```

```
rhs The sources of the data for the assignment.
```

Returns

Returns a reference to this object.

```
12.70.3.2 is_valid()

bool seq64::user_instrument::is_valid ( ) const [inline]

12.70.3.3 set_defaults()

void seq64::user_instrument::set_defaults ( )

Also invalidates the object.

12.70.3.4 name()

const std::string& seq64::user_instrument::name ( ) const [inline]

12.70.3.5 controller_count()

int seq64::user_instrument::controller_count ( ) const [inline]

12.70.3.6 controller_max()

int seq64::user_instrument::controller_max ( ) const [inline]
```

Remember that the controller numbers for each MIDI instrument range from 0 to 127 (MIDI_CONTROLLER_MAX-1).

```
12.70.3.7 controller_name()
```

```
const std::string & seq64::user_instrument::controller_name (  \qquad \qquad \text{int } c \text{ ) const}
```

c The index of the desired controller.

Returns

The name of the desired controller has is returned. If the index c is out of range, or the object is not valid, then a reference to an internal, empty string is returned.

12.70.3.8 controller_active()

```
bool seq64::user_instrument::controller_active (  \quad \text{int } c \text{ ) const}
```

Parameters

c The index of the desired controller.

Returns

The status of the desired controller has is returned. If the index c is out of range, or the object is not valid, then false is returned.

12.70.3.9 set_controller()

Parameters

С	The index of the desired controller.
cname	The name of the controller to be set as the controller name.
isactive	A flag that indicates if the desired controller is active.

12.70.3.10 set_name()

Too tricky?

Parameters

instname The name of the instrument, valid only if it is not empty
--

12.70.3.11 copy_definitions()

Does not include the validity flag.

Parameters

rhs The sources of the data for the partial copy.

12.70.4 Field Documentation

```
12.70.4.1 m_is_valid
```

```
bool seq64::user_instrument::m_is_valid [private]
```

Callers should check this flag via the is_valid() accessor before using this object. This flag is set to true when any valid member assignment occurs via a public setter call. However, setting an empty name for the instrument member will render the object invalid.

```
12.70.4.2 m_controller_count
```

```
int seq64::user_instrument::m_controller_count [private]
```

Often, the "user" configuration file has only a few out of the 128 assigned explicitly.

```
12.70.4.3 m_instrument_def
```

```
user_instrument_t seq64::user_instrument::m_instrument_def [private]
```

12.71 seq64::user_instrument_t Struct Reference

This structure corresponds to [user-instrument-N] definitions in the \sim /.seq24usr or \sim /.config/sequencer64/susr file.

Data Fields

std::string instrument

Provides the name of the "instrument" being supported.

std::string controllers [SEQ64_MIDI_CONTROLLER_MAX]

Provides a list of up to 128 controllers (e.g.

bool controllers_active [SEQ64_MIDI_CONTROLLER_MAX]

Provides a flag that indicates if each of up to 128 controller is active and supported.

12.71.1 Field Documentation

12.71.1.1 instrument

```
std::string seq64::user_instrument_t::instrument
```

Do not confuse "instrument" with "program" here. An "instrument" is most likely a hardware MIDI sound-box (though it could be a software synthesizer as well.

12.71.1.2 controllers

```
std::string seq64::user_instrument_t::controllers[SEQ64_MIDI_CONTROLLER_MAX]
```

"Modulation"). If a controller isn't present, or if General MIDI is in force, this name might be empty.

12.71.1.3 controllers active

```
bool seq64::user_instrument_t::controllers_active[SEQ64_MIDI_CONTROLLER_MAX]
```

If false, it might be an unsupported controller or a General MIDI device.

12.72 seq64::user_midi_bus Class Reference

Provides data about the MIDI busses, readable from the "user" configuration file.

Public Member Functions

user_midi_bus (const std::string &name="")

Default constructor.

user_midi_bus (const user_midi_bus &rhs)

Copy constructor.

• user_midi_bus & operator= (const user_midi_bus &rhs)

Principal assignment operator.

• bool is_valid () const

'Getter' function for member m_is_valid

void set defaults ()

Sets the default values.

• const std::string & name () const

'Getter' function for member m_midi_bus_def.alias (name of alias)

int channel_count () const

'Getter' function for member m_channel_count

• int channel_max () const

'Getter' function for member SEQ64_MIDI_BUS_CHANNEL_MAX

• int instrument (int channel) const

'Getter' function for member m_midi_bus_def.instrument[channel]

void set_instrument (int channel, int instrum)

'Getter' function for member m_midi_bus_def.instrument[channel]

Private Member Functions

• void set_name (const std::string &name)

'Setter' function for member m_midi_bus_def.alias (name of alias) Also sets the validity flag according to the emptiness of the name parameter.

void copy_definitions (const user_midi_bus &rhs)

Copies the member fields from one instance of user_midi_bus to this one.

Private Attributes

• bool m_is_valid

Provides a validity flag, useful in returning a reference to a bogus object for internal error-check.

• int m_channel_count

Provides the actual number of non-default buss channels actually set.

• user_midi_bus_t m_midi_bus_def

The instance of the structure that this class wraps.

12.72.1 Detailed Description

Will later make the size adjustable, if it makes sense to do so.

12.72.2 Constructor & Destructor Documentation

Parameters

name The name of the buss, valid only if it is not empty.

Parameters

rhs The sources of the data for the copy.

12.72.3 Member Function Documentation

12.72.3.1 operator=()

Parameters

```
rhs The sources of the data for the assignment.
```

Returns

Returns a reference to this object.

12.72.3.2 is_valid()

```
bool seq64::user_midi_bus::is_valid ( ) const [inline]
```

12.72.3.3 set_defaults()

```
void seq64::user_midi_bus::set_defaults ( )
```

Also invalidates the object. All 16 of the channels are set to SEQ64_GM_INSTRUMENT_FLAG (-1).

12.72.3.4 name()

```
const std::string& seq64::user_midi_bus::name ( ) const [inline]
```

12.72.3.5 channel_count()

```
int seq64::user_midi_bus::channel_count ( ) const [inline]
```

Returns

This function returns the number of channels. Basically this value is always the same as that returned by channel max(), but this pair of functions is consistent with the count functions in the user instrument class.

12.72.3.6 channel_max()

```
int seq64::user_midi_bus::channel_max ( ) const [inline]
```

Returns

Returns the maximum number of MIDI buss channels. Remember that the instrument channels for each MIDI buss range from 0 to 15 (MIDI_BUS_CHANNEL_MAX-1).

12.72.3.7 instrument()

Parameters

channel	Provides the desired buss channel number.	
---------	---	--

Returns

The instrument number of the desired buss channel is returned. If the channel number is out of range, or the object is not valid, then SEQ64_GM_INSTRUMENT_FLAG (-1) is returned.

12.72.3.8 set_instrument()

Does not alter the validity flag, just checks it.

Parameters

channel	Provides the desired buss channel number.
instrum	Provides the instrument number to set that channel to.

12.72.3.9 set_name()

12.72.3.10 copy_definitions()

Does not include the validity flag.

12.72.4 Field Documentation

12.72.4.1 m_is_valid

```
bool seq64::user_midi_bus::m_is_valid [private]
```

Callers should check this flag via the is_valid() accessor before using this object. This flag is set to true when any valid member assignment occurs via a public setter call.

12.72.4.2 m_channel_count

```
int seq64::user_midi_bus::m_channel_count [private]
```

Often, the "user" configuration file has only a few out of the 16 assigned explicitly.

12.72.4.3 m_midi_bus_def

```
user_midi_bus_t seq64::user_midi_bus::m_midi_bus_def [private]
```

12.73 seq64::user_midi_bus_t Struct Reference

This structure corresponds to [user-midi-bus-0] definitions in the \sim /.seq24usr ("user") file (\sim /.config/sequencer64/sequencer64.usr in the latest version of the application).

Data Fields

· std::string alias

Provides the user's desired name for the MIDI bus.

int instrument [SEQ64_MIDI_BUS_CHANNEL_MAX]

Provides an implicit list of MIDI channels from 0 to 15 (1 to 16) and the "instrument" number assigned to each channel.

12.73.1 Field Documentation

12.73.1.1 alias

```
std::string seq64::user_midi_bus_t::alias
```

For example, "2x2 A" for some kind of MIDI card or USB MIDI cable. If manual-alsa-ports is enabled, this could be something like "[0] seq24 0", and that is what should be shown in that case.

12.73.1.2 instrument

```
int seq64::user_midi_bus_t::instrument[SEQ64_MIDI_BUS_CHANNEL_MAX]
```

Note that the "instrument" is not a MIDI program number. Instead, it is the number associated with a "user-instrument" section in the "user" configuration file.

12.74 seq64::user_settings Class Reference

Holds the current values of sequence settings and settings that can modify the number of sequences and the configuration of the user-interface.

Public Member Functions

user_settings ()

Default constructor.

· user settings (const user settings &rhs)

Copy constructor.

user_settings & operator= (const user_settings &rhs)

Principal assignment operator.

· void set defaults ()

Sets the default values.

• void normalize ()

Calculate the derived values from the already-set values.

bool add_bus (const std::string &alias)

Adds a user buss to the container, but only does so if the name parameter is not empty.

bool add instrument (const std::string &instname)

Adds a user instrument to the container, but only does so if the name parameter is not empty.

const user midi bus & bus (int index)

'Getter' function for member Unlike the non-const version this function is public.

const user_instrument & instrument (int index)

'Getter' function for member Unlike the non-const version this function is public.

• int bus_count () const

'Getter' function for member m_midi_buses.size()

void set bus instrument (int index, int channel, int instrum)

'Getter' function for member m_midi_buses[index].instrument[channel] Currently this function is used, in the userfile ::parse() function.

• int bus_instrument (int buss, int channel)

'Getter' function for member m_midi_buses[buss].instrument[channel]

• const std::string & bus_name (int buss)

'Getter' function for member m_midi_buses[buss].name

· int instrument count () const

 ${\it 'Getter' function for member m_instruments.size()}$

· void set instrument controllers (int index, int cc, const std::string &ccname, bool isactive)

'Setter' function for member m_midi_instrument_defs[index].controllers, controllers_active

const std::string & instrument_name (int instrum)

'Getter' function for member m_instruments[instrument].instrument (name of instrument)

• const std::string & instrument_name (int buss, int channel)

Gets the correct instrument number from the buss and channel, and then looks up the name of the instrument.

bool instrument_controller_active (int instrum, int cc)

'Getter' function for member m_instruments[instrument].controllers_active[controller]

bool controller_active (int buss, int channel, int cc)

A convenience function so that the caller doesn't have to get the instrument number from the bus_instrument() member function.

const std::string & instrument_controller_name (int instrum, int cc)

'Getter' function for member m_instruments[instrument].controllers_active[controller]

• const std::string & controller name (int buss, int channel, int cc)

'Getter' function for member m_instruments[instrument].controllers_active[controller] A convenience function so that the caller doesn't have to get the instrument number from the bus_instrument() member function.

int grid_style () const

'Getter' function for member m_grid_style Checks for normal style.

· bool grid is normal () const

'Getter' function for member m_grid_style Checks for normal style.

· bool grid_is_white () const

'Getter' function for member m_grid_style Checks for the white style.

bool grid_is_black () const

'Getter' function for member m_grid_style Checks for the black style.

• int grid brackets () const

'Getter' function for member m_grid_brackets

• int mainwnd_rows () const

'Getter' function for member m_mainwnd_rows

int mainwnd_cols () const

'Getter' function for member m_mainwnd_cols

• int seqs_in_set () const

'Getter' function for member m_seqs_in_set, dependent member

int gmute_tracks () const

'Getter' function for member m_gmute_tracks, dependent member

int max_sets () const

'Getter' function for member m max sets

int max_sequence () const

'Getter' function for member m_max_sequence, dependent member

int text_x () const

'Getter' function for member m_text_x, not user modifiable, not saved

int text_y () const

'Getter' function for member m_text_y, not user modifiable, not saved

• int seqchars x () const

'Getter' function for member m_seqchars_x, not user modifiable, not saved

int seqchars_y () const

'Getter' function for member m_seqchars_y, not user modifiable, not saved

• int seqarea_x () const

'Getter' function for member m_seqarea_x, not user modifiable, not saved

int seqarea_y () const

'Getter' function for member m_seqarea_y, not user modifiable, not saved

• int seqarea_seq_x () const

'Getter' function for member m_seqarea_seq_x, not user modifiable, not saved

• int seqarea_seq_y () const

'Getter' function for member m_seqarea_seq_y, not user modifiable, not saved

int mainwid_border () const

'Getter' function for member m_mainwid_border

int mainwid_spacing () const

'Getter' function for member m_mainwid_spacing

int mainwid_x () const

'Getter' function for member m_mainwid_x, dependent member

int mainwid_y () const

'Getter' function for member m_mainwid_y, dependent member

• int control_height () const

'Getter' function for member m_control_height

· int zoom () const

'Getter' function for member m_current_zoom

void zoom (int value)

'Setter' function for member m_current_zoom This value is not modified unless the value parameter is between 1 and 512, inclusive.

· bool global_seq_feature () const

'Getter' function for member m_global_seq_feature_save

void global_seq_feature (bool flag)

'Setter' function for member m_global_seq_feature_save

• int seqedit_scale () const

'Getter' function for member m segedit scale

· void segedit scale (int scale)

'Setter' function for member m_seqedit_scale

• int seqedit_key () const

'Getter' function for member m_seqedit_key

void seqedit_key (int key)

'Setter' function for member m_seqedit_key

• int seqedit_bgsequence () const

'Getter' function for member m_seqedit_bgsequence

• void seqedit_bgsequence (int seqnum)

'Setter' function for member m_seqedit_bgsequence Note that SEQ64_IS_LEGAL_SEQUENCE() allows the SE← Q64_SEQUENCE_LIMIT (0x800 = 2048) value, to turn off the use of a background sequence.

bool use_new_font () const

'Getter' function for member m_use_new_font

bool allow_two_perfedits () const

'Getter' function for member m_allow_two_perfedits

• int perf_h_page_increment () const

'Getter' function for member m_h_perf_page_increment

• int perf_v_page_increment () const

'Getter' function for member m_v_perf_page_increment

• int progress_bar_colored () const

'Getter' function for member m_progress_bar_colored

· bool progress_bar_thick () const

'Getter' function for member m_progress_bar_thick

· bool inverse colors () const

Accessor m_inverse_colors

int window_redraw_rate () const

'Getter' function for member m window redraw rate ms

· bool use_more_icons () const

'Getter' function for member $m_use_more_icons$

bool save_user_config () const

'Getter' function for member m_save_user_config

void save_user_config (bool flag)

'Setter' function for member m_save_user_config

• int midi_ppqn () const

'Getter' function for member m_midi_ppqn

int midi_beats_per_bar () const

 ${\it 'Getter' function for member m_midi_beats_per_measure}$

· int midi beats per minute () const

'Getter' function for member m_midi_beats_per_minute

int midi_beat_width () const

 ${\it 'Getter' function for member m_midi_beat_width}$

· char midi buss override () const

'Getter' function for member m_midi_buss_override

• int min_zoom () const

'Getter' function for member mc_min_zoom

• int max zoom () const

'Getter' function for member mc_max_zoom

int baseline_ppqn () const

'Getter' function for member mc_baseline_ppqn

void use_new_font (bool flag)

'Setter' function for member m_use_new_font

void allow_two_perfedits (bool flag)

Sets the value of allowing two perfedits to be created and shown to the user.

void perf h page increment (int inc)

Sets the horizontal page increment size for the horizontal scrollbar of a perfedit window.

void perf_v_page_increment (int inc)

Sets the vertical page increment size for the vertical scrollbar of a perfedit window.

void progress_bar_colored (int palcode)

'Setter' function for member m_progress_bar_colored

void progress_bar_thick (bool flag)

'Setter' function for member m_progress_bar_thick

• void inverse_colors (bool flag)

'Setter' function for member m inverse colors

void window_redraw_rate (int ms)

'Setter' function for member m_window_redraw_rate_ms

void use_more_icons (bool flag)

'Setter' function for member m use more icons

void midi_ppqn (int ppqn)

'Setter' function for member m_midi_ppqn This value can be set from 96 to 19200 (this upper limit will be determined by what Sequencer64 can actually handle).

· void midi_buss_override (char buss)

'Setter' function for member m midi buss override This value can be set from 0 to 31.

Protected Member Functions

void grid brackets (int thickness)

'Getter' function for member m_grid_brackets

void grid_style (int gridstyle)

 ${\it 'Setter' function for member m_grid_style}$

void mainwnd rows (int value)

'Setter' function for member m_mainwnd_rows This value is not modified unless the value parameter is between 4 and 8, inclusive.

void mainwnd_cols (int value)

'Setter' function for member m_mainwnd_cols This value is not modified unless the value parameter is between 8 and 10. inclusive.

void max_sets (int value)

'Setter' function for member m_max_sets This value is not modified unless the value parameter is between 32 and 64, inclusive.

void text_x (int value)

'Setter' function for member m_text_x This value is not modified unless the value parameter is between 6 and 6, inclusive.

void text_y (int value)

'Setter' function for member m_text_y This value is not modified unless the value parameter is between 12 and 12, inclusive.

void seqchars_x (int value)

'Setter' function for member m_seqchars_x This affects the size or crampiness of a pattern slot, and for now we will hardwire it to 15.

void seqchars_y (int value)

'Setter' function for member m_seqchars_y This affects the size or crampiness of a pattern slot, and for now we will hardwire it to 5.

void segarea_x (int value)

'Setter' function for member m segarea x

void segarea y (int value)

'Setter' function for member m_seqarea_y

void seqarea_seq_x (int value)

'Setter' function for member m_segarea_seg_x

void seqarea_seq_y (int value)

'Setter' function for member m_seqarea_seq_y

• void mainwid border (int value)

'Setter' function for member m_mainwid_border This value is not modified unless the value parameter is between 0 and 3, inclusive.

void mainwid spacing (int value)

'Setter' function for member m_mainwid_spacing This value is not modified unless the value parameter is between 2 and 6, inclusive.

void control height (int value)

'Setter' function for member m_control_height This value is not modified unless the value parameter is between 0 and 4, inclusive.

void dump_summary ()

Provides a debug dump of basic information to help debug a surprisingly intractable problem with all busses having the name and values of the last buss in the configuration.

void midi beats per bar (int beatsperbar)

'Setter' function for member m_midi_beats_per_measure This value can be set from 1 to 16.

• void midi_beats_per_minute (int beatsperminute)

'Setter' function for member m_midi_beats_minute This value can be set from 20 to 500.

void midi_beat_width (int beatwidth)

'Setter' function for member m_midi_beatwidth This value can be set to any power of 2 in the range from 1 to 16.

Private Types

```
    enum mainwid_grid_style_t {
        grid_style_normal,
        grid_style_white,
        grid_style_black,
        grid_style_max }
```

typedef std::vector< user_midi_bus > Busses

[user-midi-bus-definitions]

- typedef std::vector< user midi bus >::iterator BussIterator
- typedef std::vector< user_midi_bus >::const_iterator BussConstIterator
- typedef std::vector< user_instrument > Instruments

[user-instrument-definitions]

- typedef std::vector< user instrument >::iterator InstrumentIterator
- typedef std::vector< user_instrument >::const_iterator InstrumentConstIterator

Private Member Functions

user_midi_bus & private_bus (int buss)

'Getter' function for member m_midi_buses[index] (internal function) If the index is out of range, then an invalid object is returned.

user_instrument & private_instrument (int instrum)

'Getter' function for member m_instruments[index] If the index is out of range, then a invalid object is returned.

Private Attributes

• Busses m_midi_buses

Provides data about the MIDI busses, readable from the "user" configuration file.

· Instruments m instruments

Provides data about the MIDI instruments, readable from the "user" configuration file.

• mainwid_grid_style_t m_grid_style

[user-interface-settings]

· int m grid brackets

Specify drawing brackets (like the old Seq24) or a solid box.

· int m mainwnd rows

Number of rows in the Patterns Panel.

· int m mainwnd cols

Number of columns in the Patterns Panel.

• int m_max_sets

Maximum number of screen sets that can be supported.

· int m mainwid border

These control sizes.

- · int m_mainwid_spacing
- · int m control height

This constants seems to be created for a future purpose, perhaps to reserve space for a new bar on the mainwid pane.

int m_current_zoom

Provides the initial zoom value, in units of ticks per pixel.

bool m_global_seq_feature_save

If true, this value provide a bit of backward-compatibility with the global key/scale/background-sequence persistence feature.

· int m_seqedit_scale

Replaces sequence is loaded into the sequence editor.

· int m segedit key

Replaces seqedit::m_initial_key as the repository for the key to apply when a sequence is loaded into the sequence editor.

• int m_seqedit_bgsequence

Replaces sequedit::m_initial_sequence as the repository for the background sequence to apply when a sequence is loaded into the sequence editor.

· bool m use new font

Sets the usage of the font.

bool m_allow_two_perfedits

Enables the usage of two perfedit windows, for added convenience in editing multi-set songs.

• int m_h_perf_page_increment

Allows a changed to the page size for the horizontal scroll bar.

int m_v_perf_page_increment

Allows a changed to the page size for the vertical scroll bar.

· int m_progress_bar_colored

If set, makes progress bars have the "progress_color()", instead of black.

bool m_progress_bar_thick

If set, makes progress bars thicker than 1 pixel...

· bool m inverse colors

If set, use an alternate, neo-inverse color palette.

• int m window redraw rate ms

Provides the global setting for redraw rate of windows.

• bool m_use_more_icons

Another [user-interface-settings] item.

int m_text_x

Constants for the mainwid class.

- int m_text_y
- · int m seqchars x

Constants for the mainwid class.

- · int m_seqchars_y
- int m_midi_ppqn

Provides the universal PPQN setting for the duration of this setting.

• int m_midi_beats_per_measure

Provides the universal and unambiguous MIDI value for beats per measure, also called "beats per bar" (BPB).

· int m midi beats per minute

Provides the universal and unambiguous MIDI value for beats per minute (BPM).

• int m_midi_beat_width

Provides the universal MIDI value for beats width (BW).

· char m midi buss override

Provides a universal override of the buss number for all sequences, for the purpose of convenience of of testing.

- int m total segs
- · int m_seqs_in_set

Number of patterns/sequences in the Patterns Panel, also known as a "set" or "screen set".

• int m_gmute_tracks

Number of group-mute tracks that can be supported, which is m_seqs_in_set squared, or 1024.

int m_max_sequence

The maximum number of patterns supported is given by the number of patterns supported in the panel (32) times the maximum number of sets (32), or 1024 patterns.

int m_seqarea_x

The m_seqarea_x and m_seqarea_y constants are derived from the width and heights of the default character set, and the number of characters in width, and the number of lines, in a pattern/sequence box.

- int m_seqarea_y
- int m_seqarea_seq_x

Area of what? Doesn't look at all like it is based on the size of characters.

- int m_seqarea_seq_y
- int m_mainwid_x

The width of the main pattern/sequence grid, in pixels.

- · int m mainwid y
- · bool m_save_user_config

Provides a temporary variable that can be set from the command line to cause the "user" state to be saved into the "user" configuration file.

· const int mc min zoom

Provides the minimum zoom value, currently a constant.

· const int mc max zoom

Provides the maximum zoom value, currently a constant.

const int mc_baseline_ppqn

Permanent storage for the baseline, default PPQN used by Seq24.

Friends

· class userfile

12.74.1 Detailed Description

These settings will eventually be made part of the "user" settings file.

12.74.2 Member Typedef Documentation

12.74.2.1 Busses

```
typedef std::vector<user_midi_bus> seq64::user_settings::Busses [private]
```

Internal type for the container of user_midi_bus objects. Sorry about the "confusion" about "bus" versus "buss". See Google for arguments about it.

12.74.2.2 BussIterator

```
typedef std::vector<user_midi_bus>::iterator seq64::user_settings::BussIterator [private]
```

12.74.2.3 BussConstIterator

typedef std::vector<user_midi_bus>::const_iterator seq64::user_settings::BussConstIterator
[private]

12.74.2.4 Instruments

```
typedef std::vector<user_instrument> seq64::user_settings::Instruments [private]
```

Internal type for the container of user_instrument objects.

12.74.2.5 InstrumentIterator

```
typedef std::vector<user_instrument>::iterator seq64::user_settings::InstrumentIterator [private]
```

12.74.2.6 InstrumentConstiterator

```
\label{typedef} \begin{tabular}{ll} typedef std::vector < user_instrument > ::const_iterator seq 64::user_settings::Instrument Const \leftarrow Iterator [private] \end{tabular}
```

12.74.3 Member Enumeration Documentation

12.74.3.1 mainwid_grid_style_t

```
enum seq64::user_settings::mainwid_grid_style_t [private]
```

Enumerator

grid_style_normal	
The grid background color is white. This style better fits displaying the white-on-black	
sequence numbers. The box is drawn with brackets on either side.	
grid_style_black	The grid background color is black.
grid_style_max	Marks the end of the list, and is an illega

12.74.4 Constructor & Destructor Documentation

```
12.74.4.1 user_settings() [1/2]
seq64::user_settings::user_settings ( )
12.74.4.2 user_settings() [2/2]
seq64::user_settings::user_settings (
             const user_settings & rhs )
12.74.5 Member Function Documentation
```

12.74.5.1 operator=()

```
user_settings & seq64::user_settings::operator= (
             const user_settings & rhs )
12.74.5.2 set_defaults()
void seq64::user_settings::set_defaults ( )
```

For the m_midi_buses and m_instruments members, this function can only iterate over the current size of the vectors. But the default size is zero!

12.74.5.3 normalize()

```
void seq64::user_settings::normalize ( )
12.74.5.4 add_bus()
bool seq64::user_settings::add_bus (
```

const std::string & alias)

```
12.74.5.5 add_instrument()
bool seq64::user_settings::add_instrument (
            const std::string & instname )
12.74.5.6 bus()
const user_midi_bus& seq64::user_settings::bus (
             int index ) [inline]
Cannot append the const specifier.
12.74.5.7 instrument()
const user_instrument& seq64::user_settings::instrument (
             int index ) [inline]
Cannot append the const specifier.
12.74.5.8 bus_count()
int seq64::user_settings::bus_count ( ) const [inline]
12.74.5.9 set_bus_instrument()
void seq64::user_settings::set_bus_instrument (
             int index,
             int channel,
             int instrum )
12.74.5.10 bus_instrument()
int seq64::user_settings::bus_instrument (
             int buss,
             int channel ) [inline]
12.74.5.11 bus_name()
const std::string& seq64::user_settings::bus_name (
             int buss ) [inline]
12.74.5.12 instrument_count()
int seq64::user_settings::instrument_count ( ) const [inline]
```

12.74.5.13 set_instrument_controllers()

```
void seq64::user_settings::set_instrument_controllers (
             int index,
             int cc,
             const std::string & ccname,
             bool isactive )
12.74.5.14 instrument_name() [1/2]
const std::string& seq64::user_settings::instrument_name (
             int instrum ) [inline]
12.74.5.15 instrument_name() [2/2]
const std::string& seq64::user_settings::instrument_name (
             int buss,
             int channel ) [inline]
12.74.5.16 instrument_controller_active()
bool seq64::user\_settings::instrument\_controller\_active (
             int instrum,
             int cc ) [inline]
12.74.5.17 controller_active()
bool seq64::user_settings::controller_active (
             int buss,
             int channel,
             int cc ) [inline]
It also has a shorter name.
12.74.5.18 instrument_controller_name()
const std::string& seq64::user_settings::instrument_controller_name (
             int instrum,
             int cc ) [inline]
12.74.5.19 controller_name()
const std::string& seq64::user_settings::controller_name (
             int buss,
             int channel,
             int \ cc ) [inline]
```

It also has a shorter name.

```
12.74.5.20 grid_style() [1/2]
int seq64::user_settings::grid_style ( ) const [inline]
12.74.5.21 grid_is_normal()
bool seq64::user_settings::grid_is_normal ( ) const [inline]
12.74.5.22 grid_is_white()
bool seq64::user_settings::grid_is_white ( ) const [inline]
12.74.5.23 grid_is_black()
bool seq64::user_settings::grid_is_black ( ) const [inline]
12.74.5.24 grid_brackets() [1/2]
int seq64::user_settings::grid_brackets ( ) const [inline]
12.74.5.25 mainwnd_rows() [1/2]
int seq64::user_settings::mainwnd_rows ( ) const [inline]
12.74.5.26 mainwnd_cols() [1/2]
int seq64::user_settings::mainwnd_cols ( ) const [inline]
12.74.5.27 seqs_in_set()
int seq64::user_settings::seqs_in_set ( ) const [inline]
12.74.5.28 gmute_tracks()
int seq64::user_settings::gmute_tracks ( ) const [inline]
12.74.5.29 max_sets() [1/2]
int seq64::user_settings::max_sets ( ) const [inline]
```

```
12.74.5.30 max_sequence()
int seq64::user_settings::max_sequence ( ) const [inline]
12.74.5.31 text_x() [1/2]
int seq64::user_settings::text_x ( ) const [inline]
12.74.5.32 text_y() [1/2]
int seq64::user_settings::text_y ( ) const [inline]
12.74.5.33 seqchars_x() [1/2]
int seq64::user\_settings::seqchars\_x ( ) const [inline]
12.74.5.34 seqchars_y() [1/2]
int seq64::user_settings::seqchars_y ( ) const [inline]
12.74.5.35 segarea_x() [1/2]
int seq64::user_settings::seqarea_x ( ) const [inline]
12.74.5.36 seqarea_y() [1/2]
int seq64::user_settings::seqarea_y ( ) const [inline]
12.74.5.37 seqarea_seq_x() [1/2]
int seq64::user_settings::seqarea_seq_x ( ) const [inline]
12.74.5.38 seqarea_seq_y() [1/2]
int seq64::user_settings::seqarea_seq_y ( ) const [inline]
12.74.5.39 mainwid_border() [1/2]
int seq64::user_settings::mainwid_border ( ) const [inline]
```

```
12.74.5.40 mainwid_spacing() [1/2]
int seq64::user_settings::mainwid_spacing ( ) const [inline]
12.74.5.41 mainwid_x()
int seq64::user_settings::mainwid_x ( ) const [inline]
12.74.5.42 mainwid_y()
int seq64::user_settings::mainwid_y ( ) const [inline]
12.74.5.43 control_height() [1/2]
int seq64::user_settings::control_height ( ) const [inline]
12.74.5.44 zoom() [1/2]
int seq64::user_settings::zoom ( ) const [inline]
12.74.5.45 zoom() [2/2]
void seq64::user_settings::zoom (
             int value )
The default value is 2. Note that 0 is allowed as a special case, which allows the default zoom to be adjusted when
the PPQN value is different from the default.
12.74.5.46 global_seq_feature() [1/2]
bool seq64::user_settings::global_seq_feature ( ) const [inline]
12.74.5.47 global_seq_feature() [2/2]
void seq64::user_settings::global_seq_feature (
             bool flag ) [inline]
12.74.5.48 seqedit_scale() [1/2]
int seq64::user_settings::seqedit_scale ( ) const [inline]
```

```
12.74.5.49 seqedit_scale() [2/2]
void seq64::user_settings::seqedit_scale (
            int scale ) [inline]
12.74.5.50 seqedit_key() [1/2]
int seq64::user_settings::seqedit_key ( ) const [inline]
12.74.5.51 seqedit_key() [2/2]
void seq64::user_settings::seqedit_key (
            int key ) [inline]
12.74.5.52 seqedit_bgsequence() [1/2]
int seq64::user_settings::seqedit_bgsequence ( ) const [inline]
12.74.5.53 seqedit_bgsequence() [2/2]
void seq64::user_settings::seqedit_bgsequence (
             int seqnum ) [inline]
12.74.5.54 use_new_font() [1/2]
bool seq64::user_settings::use_new_font ( ) const [inline]
12.74.5.55 allow_two_perfedits() [1/2]
bool seq64::user_settings::allow_two_perfedits ( ) const [inline]
12.74.5.56 perf_h_page_increment() [1/2]
int seq64::user_settings::perf_h_page_increment ( ) const [inline]
12.74.5.57 perf_v_page_increment() [1/2]
int seq64::user_settings::perf_v_page_increment ( ) const [inline]
12.74.5.58 progress_bar_colored() [1/2]
int seq64::user_settings::progress_bar_colored ( ) const [inline]
```

```
12.74.5.59 progress_bar_thick() [1/2]
bool seq64::user_settings::progress_bar_thick ( ) const [inline]
12.74.5.60 inverse_colors() [1/2]
bool seq64::user_settings::inverse_colors ( ) const [inline]
12.74.5.61 window_redraw_rate() [1/2]
int seq64::user_settings::window_redraw_rate ( ) const [inline]
12.74.5.62 use_more_icons() [1/2]
bool seq64::user_settings::use_more_icons ( ) const [inline]
12.74.5.63 save_user_config() [1/2]
bool seq64::user_settings::save_user_config ( ) const [inline]
12.74.5.64 save_user_config() [2/2]
void seq64::user_settings::save_user_config (
             bool flag ) [inline]
12.74.5.65 grid_brackets() [2/2]
void seq64::user_settings::grid_brackets (
             int thickness ) [inline], [protected]
12.74.5.66 grid_style() [2/2]
void seq64::user_settings::grid_style (
             int gridstyle ) [protected]
12.74.5.67 mainwnd_rows() [2/2]
void seq64::user_settings::mainwnd_rows (
            int value ) [protected]
```

The default value is 4. Dependent values are recalculated after the assignment.

The default value is 8. Dependent values are recalculated after the assignment.

The default value is 32. Dependent values are recalculated after the assignment.

The default value is 6. Dependent values are recalculated after the assignment. This value is currently restricted, until we can code up a bigger font.

The default value is 12. Dependent values are recalculated after the assignment. This value is currently restricted, until we can code up a bigger font.

```
12.74.5.75 seqarea_y() [2/2]
void seq64::user_settings::seqarea_y (
            int value ) [protected]
12.74.5.76 seqarea_seq_x() [2/2]
void seq64::user_settings::seqarea_seq_x (
             int value ) [protected]
12.74.5.77 seqarea_seq_y() [2/2]
void seq64::user_settings::seqarea_seq_y (
             int value ) [protected]
12.74.5.78 mainwid_border() [2/2]
void seq64::user_settings::mainwid_border (
             int value ) [protected]
The default value is 0. Dependent values are recalculated after the assignment.
12.74.5.79 mainwid_spacing() [2/2]
void seq64::user_settings::mainwid_spacing (
             int value ) [protected]
The default value is 2. Dependent values are recalculated after the assignment.
12.74.5.80 control_height() [2/2]
void seq64::user_settings::control_height (
             int value ) [protected]
The default value is 0. Dependent values are recalculated after the assignment.
12.74.5.81 dump_summary()
void seq64::user_settings::dump_summary ( ) [protected]
Does its work only if PLATFORM DEBUG and SEQ64 USE DEBUG OUTPUT are defined. Only enabled in
emergencies :-D.
12.74.5.82 midi_ppqn() [1/2]
int seq64::user_settings::midi_ppqn ( ) const [inline]
```

```
12.74.5.83 midi_beats_per_bar() [1/2]
int seq64::user_settings::midi_beats_per_bar ( ) const [inline]
12.74.5.84 midi_beats_per_minute() [1/2]
int seq64::user_settings::midi_beats_per_minute ( ) const [inline]
12.74.5.85 midi_beat_width() [1/2]
int seq64::user_settings::midi_beat_width ( ) const [inline]
12.74.5.86 midi_buss_override() [1/2]
char seq64::user_settings::midi_buss_override ( ) const [inline]
12.74.5.87 min_zoom()
int seq64::user_settings::min_zoom ( ) const [inline]
12.74.5.88 max_zoom()
int seq64::user_settings::max_zoom ( ) const [inline]
12.74.5.89 baseline_ppqn()
int seq64::user_settings::baseline_ppqn ( ) const [inline]
12.74.5.90 use_new_font() [2/2]
void seq64::user_settings::use_new_font (
             bool flag ) [inline]
12.74.5.91 allow_two_perfedits() [2/2]
void seq64::user_settings::allow_two_perfedits (
             bool flag ) [inline]
```

```
12.74.5.92 perf_h_page_increment() [2/2]
void seq64::user_settings::perf_h_page_increment (
    int inc)
```

This value ranges from 1 (the original value, really too small for a "page" operation) to 6 (which is 24 measures, the same as the typical width of the perfroll)

```
12.74.5.93 perf_v_page_increment() [2/2]
void seq64::user_settings::perf_v_page_increment (
    int inc)
```

This value ranges from 1 (the original value, really too small for a "page" operation) to 18 (which is 18 tracks, slightly more than the typical height of the perfroll)

```
12.74.5.94 progress_bar_colored() [2/2]
void seq64::user_settings::progress_bar_colored (
             int palcode ) [inline]
12.74.5.95 progress_bar_thick() [2/2]
void seq64::user_settings::progress_bar_thick (
             bool flag ) [inline]
12.74.5.96 inverse_colors() [2/2]
void seq64::user_settings::inverse_colors (
            bool flag ) [inline]
12.74.5.97 window_redraw_rate() [2/2]
void seq64::user_settings::window_redraw_rate (
            int ms ) [inline]
12.74.5.98 use_more_icons() [2/2]
void seq64::user_settings::use_more_icons (
            bool flag ) [inline]
12.74.5.99 midi_ppqn() [2/2]
void seq64::user_settings::midi_ppqn (
             int value )
```

The default value is 192.

The default value is -1, which means that there is no buss override. It provides a way to override the buss number for smallish MIDI files. It replaces the buss-number read from the file. This option is turned on by the —bus option, and is merely a convenience feature for the quick previewing of a tune. (It's called "developer laziness".)

This invalid object has an empty alias, and all the instrument numbers are -1.

```
12.74.5.105 private_instrument()
user_instrument & seq64::user_settings::private_instrument (
```

int index) [private]

This invalid object has an empty(), instrument name, false for all controllers_active[] values, and empty controllers[] string values.

12.74.6 Friends And Related Function Documentation

12.74.6.1 userfile

```
friend class userfile [friend]
```

12.74.7 Field Documentation

12.74.7.1 m_midi_buses

```
Busses seq64::user_settings::m_midi_buses [private]
```

Since this object is a vector, its size is adjustable.

12.74.7.2 m_instruments

```
Instruments seq64::user_settings::m_instruments [private]
```

The size is adjustable, and grows as objects are added.

12.74.7.3 m_grid_style

```
mainwid_grid_style_t seq64::user_settings::m_grid_style [private]
```

These are not labelled, but are present in the "user" configuration file in the following order:

```
-# grid-style
-# grid-brackets
-# mainwnd-rows
-# mainwnd-cols
-# max-set
-# mainwid-border
-# control-height
-# zoom
-# global-seq-feature
-# use-new-font
-# allow-two-perfedits
-# perf-h-page-increment
-# perf-v-page-increment
-# progress-bar-colored (new)
-# progress-bar-thick (new)
-# window-redraw-rate-ms (new)
```

Specifies the current grid style.

12.74.7.4 m_grid_brackets

```
int seq64::user_settings::m_grid_brackets [private]
```

0 = no brackets, 1 and above is the thickness of the brakets. 1 is the normal thickness of the brackets, 2 is a two-pixel thickness, and so on.

12.74.7.5 m_mainwnd_rows

```
int seq64::user_settings::m_mainwnd_rows [private]
```

The current value is 4, and if changed, many other values depend on it. Together with m_mainwnd_cols, this value fixes the patterns grid into a 4 x 8 set of patterns known as a "screen set". We would like to be able to change this value from 4 to 8, and maybe allow the values of 5, 6, and 7 as well. But if we could just get 8 working, then well would Sequencer64 deserve the 64 in its name.

12.74.7.6 m mainwnd cols

```
int seq64::user_settings::m_mainwnd_cols [private]
```

The current value is 4, and probably won't change, since other values depend on it. Together with m_mainwnd_rows, this value fixes the patterns grid into a 4 x 8 set of patterns known as a "screen set".

12.74.7.7 m_max_sets

```
int seq64::user_settings::m_max_sets [private]
```

Basically, that the number of times the Patterns Panel can be filled. 32 sets can be created. Although this value is part of the "user" configuration file, it is likely that it will never change. Rather, the number of sequences per set would change. We'll see.

12.74.7.8 m_mainwid_border

```
int seq64::user_settings::m_mainwid_border [private]
```

We'll try changing them and see what happens. Increasing these value spreads out the pattern grids a little bit and makes the Patterns panel slightly bigger. Seems like it would be useful to make these values user-configurable.

12.74.7.9 m_mainwid_spacing

```
int seq64::user_settings::m_mainwid_spacing [private]
```

12.74.7.10 m_control_height

```
int seq64::user_settings::m_control_height [private]
```

But it is used only in this header file, to define m_mainwid_y, but doesn't add anything to that value.

12.74.7.11 m_current_zoom

```
int seq64::user_settings::m_current_zoom [private]
```

The original default value was 32 ticks per pixel, but larger PPQN values need higher values, and we will have to adapt the default zoom to the PPQN value. Also, the zoom can never be zero, as it can appear as the divisor in scaling equations.

12.74.7.12 m_global_seq_feature_save

```
bool seq64::user_settings::m_global_seq_feature_save [private]
```

In this feature, applying one of these three changes to a sequence causes them to also be applied to sequences that are subsequently opened for editing. However, we improve on this feature by allowing the changes to be saved in the global, proprietary part of the saved MIDI file.

If false, the user can still save the key/scale/background-sequence values with each individual sequence, so they can be different.

This value will be true by default, unless changed in the "user" configuration file.

12.74.7.13 m_seqedit_scale

```
int seq64::user_settings::m_seqedit_scale [private]
```

Its default value is c_scale_off. Although this value is now stored in the user_settings class, it always comes from the currently loaded MIDI file, if present. If m_global_seq_feature_save is true, this variable is stored in the "proprietary" track at the end of the file, under the control tag c_musicscale, and will be applied to any sequence that is edited. If m_global_seq_feature_save is false, this variable is stored, if used, in the meta-data for the sequence to which it applies, and, again, is tagged with the control tag c_musicscale.

12.74.7.14 m_seqedit_key

```
int seq64::user_settings::m_seqedit_key [private]
```

Its default value is SEQ64_KEY_OF_C. Although this value is now stored in the user_settings class, it always comes from the currently loaded MIDI file, if present. If m_global_seq_feature_save is true, this variable is stored in the "proprietary" track at the end of the file, under the control tag c_musickey, and will be applied to any sequence that is edited. If m_global_seq_feature_save is false, this variable is stored, if used, in the meta-data for the sequence to which it applies, and, again, is tagged with the control tag c_musickey.

12.74.7.15 m_seqedit_bgsequence

```
int seq64::user_settings::m_seqedit_bgsequence [private]
```

Its default value is SEQ64_SEQUENCE_LIMIT. Although this value is now stored in the user_settings class, it always comes from the currently loaded MIDI file, if present. If m_global_seq_feature_save is true, this variable is stored, if it has a valid (but not "legal") value, in the "proprietary" track at the end of the file, under the control tag c_backsequence, and will be applied to any sequence that is edited. If m_global_seq_feature_save is false, this variable is stored, if used, in the meta-data for the sequence to which it applies, and, again, is tagged with the control tag c_backsequence.

12.74.7.16 m_use_new_font

```
bool seq64::user_settings::m_use_new_font [private]
```

By default, in normal mode, the new font is used. In legacy mode, the old font is used.

12.74.7.17 m_allow_two_perfedits

```
bool seq64::user_settings::m_allow_two_perfedits [private]
```

Defaults to true.

12.74.7.18 m_h_perf_page_increment

```
int seq64::user_settings::m_h_perf_page_increment [private]
```

The value used to be hardwired to 1 (in four-measure units), now it defaults to 4 (16 measures at a time). The value of 1 is already covered by the scrollbar arrows.

12.74.7.19 m_v_perf_page_increment

```
int seq64::user_settings::m_v_perf_page_increment [private]
```

The value used to be hardwired to 1 (in single-track units), now it defaults to 8. The value of 1 is already covered by the scrollbar arrows.

12.74.7.20 m_progress_bar_colored

```
int seq64::user_settings::m_progress_bar_colored [private]
```

This value is no longer hardwired in the gui_palette_gtk2 module to be red. Now we want to let the color select from a slightly large palette. We chande this from a boolean to an integer to allow the selection of more colors.

12.74.7.21 m_progress_bar_thick

```
bool seq64::user_settings::m_progress_bar_thick [private]
```

2 pixels. It isn't useful to support anything thicker.

12.74.7.22 m_inverse_colors

```
bool seq64::user_settings::m_inverse_colors [private]
```

Not all colors are reversed, though.

12.74.7.23 m_window_redraw_rate_ms

```
int seq64::user_settings::m_window_redraw_rate_ms [private]
```

Not all windows use this yet. The default is 40 ms (c_redraw_ms, which is 20 ms in Windows builds)), but some windows originally used 25 ms, so beware of side-effects.

```
12.74.7.24 m_use_more_icons
```

```
bool seq64::user_settings::m_use_more_icons [private]
```

If set to 1, icons will be used for more buttons. This setting affects only a few buttons so far, such as the buttons at the top of the main window.

12.74.7.25 m_text_x

```
int seq64::user_settings::m_text_x [private]
```

The m_text_x and m_text_y constants help define the "seqarea" size. It looks like these two values are the character width (x) and height (y) in pixels. Thus, these values would be dependent on the font chosen. But that, currently, is hard-wired. See the m_font_6_12[] array for the default font specification.

However, please not that font files are not used. Instead, the fonts are provided by two pixmaps in the src/pixmap directory: font_b.xpm (black lettering on a white background) and font_w.xpm (white lettering on a black background).

We have added black-on-yellow and yellow-on-black versions of the fonts, to support the highlighting of pattern boxes if they are empty of actual MIDI events.

We have also added a set of four new font files that are roughly the same size, and are treated as the same size, but look smooth and less like a DOS-era font.

The font module does not use these values directly, but does define some similar variables that differ slightly between the two styles of font. There are a lot of tricks and hard-wired places to fix before further work can be done with fonts in Sequencer64.

12.74.7.26 m text y

```
int seq64::user_settings::m_text_y [private]
```

12.74.7.27 m_seqchars_x

```
int seq64::user_settings::m_seqchars_x [private]
```

The m_seqchars_x and m_seqchars_y constants help define the "seqarea" size. These look like the number of characters per line and the number of lines of characters, in a pattern/sequence box.

12.74.7.28 m_seqchars_y

```
int seq64::user_settings::m_seqchars_y [private]
```

12.74.7.29 m_midi_ppqn

```
int seq64::user_settings::m_midi_ppqn [private]
```

This variable replaces the global ppqn. The default value of this setting is 192 parts-per-quarter-note (PPQN). There is still a lot of work to get a different PPQN to work properly in speed of playback, scaling of the user interface, and other issues. Note that this value can be changed by the still-experimental –ppqn option. There is one remaining trace of the global, though: DEFAULT_PPQN.

12.74.7.30 m_midi_beats_per_measure

```
int seq64::user_settings::m_midi_beats_per_measure [private]
```

This variable will replace the global beats per measure. The default value of this variable is SEQ64_DEFAULT_← BEATS_PER_MEASURE (4). For external access, we will call this value "beats per bar", abbreviate it "BPB", and use "bpb" in any accessor function names. Now, although it applies to the whole session, we should be able to continue seq24's tradition of allowing each sequence to have its own time signature. Also, there are a number of places where the number 4 appears and looks like it might be a hardwired BPB value, either for MIDI purposes or for drawing the piano-roll grids. So we might need a couple different versions of this variable.

12.74.7.31 m_midi_beats_per_minute

```
int seq64::user_settings::m_midi_beats_per_minute [private]
```

This variable will replace the global beats per minute. The default value of this variable is DEFAULT_BPM (120). This variable should apply to the whole session; there's probably no way to support a diffent tempo for each sequence. But we shall see. For external access, we will call this value "beats per minute", abbreviate it "BPM", and use "bpm" in any accessor function names.

12.74.7.32 m_midi_beat_width

```
int seq64::user_settings::m_midi_beat_width [private]
```

This variable will replace the global beat_width. The default value of this variable is DEFAULT_BEAT_WIDTH (4). Now, although it applies to the whole session, we should be able to continue seq24's tradition of allowing each sequence to have its own time signature. Also, there are a number of places where the number 4 appears and looks like it might be a hardwired BW value, either for MIDI purposes or for drawing the user-interface. So we might need a couple different versions of this variable. For external access, we will call this value "beat width", abbreviate it "BW", and use "bw" in any accessor function names.

12.74.7.33 m_midi_buss_override

```
char seq64::user_settings::m_midi_buss_override [private]
```

This variable replaces the global buss-override variable, and is set via the command-line option -bus.

12.74.7.34 m_total_seqs

```
int seq64::user_settings::m_total_seqs [private]
```

12.74.7.35 m_seqs_in_set

```
int seq64::user_settings::m_seqs_in_set [private]
```

This value is $4 \times 8 = 32$ by default.

Warning

Currently implicit/explicit in a number of the "rc" file and rc_settings. Would probably want the left 32 or the first 32 items in the main window only to be subject to keystroke control. This value is calculated by the normalize() function, and is *not* part of the "user" configuration file.

```
12.74 seq64::user_settings Class Reference
12.74.7.36 m_gmute_tracks
int seq64::user_settings::m_gmute_tracks [private]
This value is not part of the "user" configuration file; it is calculated by the normalize() function.
12.74.7.37 m_max_sequence
int seq64::user_settings::m_max_sequence [private]
It is a derived value, and not stored in the "user" file.
m_max_sequence = m_seqs_in_set * m_max_sets;
12.74.7.38 m_seqarea_x
int seq64::user_settings::m_seqarea_x [private]
Compare these two constants to m_seqarea_seq_x(y), which was in mainwid.h, but is now in this file.
12.74.7.39 m_seqarea_y
int seq64::user_settings::m_seqarea_y [private]
12.74.7.40 m_seqarea_seq_x
int seq64::user_settings::m_seqarea_seq_x [private]
These are used only in the mainwid module.
12.74.7.41 m_seqarea_seq_y
int seq64::user_settings::m_seqarea_seq_y [private]
12.74.7.42 m_mainwid_x
int seq64::user_settings::m_mainwid_x [private]
```

```
c_mainwid_x =
    (c_seqarea_x + c_mainwid_spacing) * c_mainwnd_cols -
        c_mainwid_spacing + c_mainwid_border * 2
);
```

Affected by the m_mainwid_border and m_mainwid_spacing values.

12.74.7.43 m_mainwid_y

```
int seq64::user_settings::m_mainwid_y [private]
```

12.74.7.44 m_save_user_config

```
bool seq64::user_settings::m_save_user_config [private]
```

Normally, this state is not saved. It is not saved because there is currently no user-interface for editing it, and because it can pick up some command-line options, and it is not right to have them written to the "user" configuration file.

(The "rc" configuration file is a different case, having historically always been saved, and having a number of command-line options, such as JACK settings that should generally be permanent on a given system.)

Anyway, this flag can be set by the –user-save option. This setting is never saved. But note that, if no "user" configuration file is found, it is then saved anyway.

12.74.7.45 mc_min_zoom

```
const int seq64::user_settings::mc_min_zoom [private]
```

It's value is 1.

12.74.7.46 mc_max_zoom

```
const int seq64::user_settings::mc_max_zoom [private]
```

It's value was 32, but is now 512, to allow for better presentation of high PPQN valued sequences.

12.74.7.47 mc_baseline_ppqn


```
const int seq64::user_settings::mc_baseline_ppqn [private]
```

This value is necessary in order to keep user-interface elements stable when different PPQNs are used. It is set to DEFAULT_PPQN.

12.75 seq64::userfile Class Reference

Supports the user's \sim /.config/sequencer64/sequencer64.usr and \sim /.seq24usr configuration file.

Inheritance diagram for seq64::userfile:



Public Member Functions

• userfile (const std::string &a_name)

Principal constructor.

• ∼userfile ()

A rote destructor needed for a derived class.

• bool parse (perform &a_perf)

Parses a "usr" file, filling in the given perform object.

• bool write (const perform &a_perf)

This function just returns false, as there is no "perform" information in the user-file yet.

Private Member Functions

• void dump_setting_summary ()

Provides a debug dump of basic information to help debug a surprisingly intractable problem with all busses having the name and values of the last buss in the configuration.

Additional Inherited Members

12.75.1 Constructor & Destructor Documentation

12.75.1.1 userfile()

Parameters

name

Provides the full file path specification to the configuration file.

```
12.75.1.2 ∼userfile()
```

```
seq64::userfile::~userfile ( )
```

12.75.2 Member Function Documentation

12.75.2.1 parse()

This function opens the file as a text file (line-oriented).

Parameters

Returns

Returns true if the parsing succeeded.

Implements seq64::configfile.

12.75.2.2 write()

Parameters

a_perf The performance object, currently unused.

Returns

Returns true if the writing succeeded.

Implements seq64::configfile.

12.75.2.3 dump_setting_summary()

void seq64::userfile::dump_setting_summary () [private]

Does work only if PLATFORM_DEBUG is defined; see the user_settings class.

Index

~AbstractPerfInput	seq64::midi_splitter, 386
seq64::AbstractPerfInput, 102	\sim midi_vector
\sim automutex	seq64::midi_vector, 393
seq64::automutex, 105	\sim midibus
\sim configfile	seq64::midibus, 398
seq64::configfile, 113	\sim midifile
~editable_event	seq64::midifile, 407
seq64::editable_event, 121	\sim optionsfile
~editable_events	seq64::optionsfile, 431
seq64::editable_events, 131	\sim perfedit
~event	seq64::perfedit, 440
seq64::event, 141	\sim perfnames
~event_list	seq64::perfnames, 454
seq64::event_list, 158	\sim perform
~eventedit	seq64::perform, 472
seq64::eventedit, 170	\sim perfroll
~eventslots	seq64::perfroll, 535
seq64::eventslots, 184	\sim perftime
~gui_assistant	seq64::perftime, 552
seq64::gui_assistant, 213	\sim seqdata
~gui_assistant_gtk2	seq64::seqdata, 586
seq64::gui_assistant_gtk2, 215	\sim seqedit
~gui_drawingarea_gtk2	seq64::seqedit, 601
seq64::gui_drawingarea_gtk2, 220	\sim seqevent
~gui_palette_gtk2	seq64::seqevent, 625
seq64::gui_palette_gtk2, 238	\sim seqkeys
~gui_window_gtk2	seq64::seqkeys, 639
seq64::gui_window_gtk2, 245	\sim seqmenu
~jack_assistant	seq64::seqmenu, 649
seq64::jack_assistant, 252	\sim seqroll
~keys_perform	seq64::seqroll, 661
seq64::keys_perform, 281	\sim seqtime
~keys perform gtk2	seq64::seqtime, 686
seq64::keys_perform_gtk2, 302	\sim sequence
~Ifownd	seq64::sequence, 701
seq64::lfownd, 315	~triggers
~maintime	seq64::triggers, 760
seq64::maintime, 320	~userfile
~mainwid	seq64::userfile, 812
seq64::mainwid, 326	about dialog
~mainwnd	about_dialog
seq64::mainwnd, 342	seq64::mainwnd, 346 AbstractPerfInput
~mastermidibus	seq64::AbstractPerfInput, 102
seq64::mastermidibus, 356	activate_adding
~midi container	
seq64::midi_container, 369	seq64::AbstractPerfInput, 103 seq64::FruityPerfInput, 206
~midi_list	seq64::FruityPerflirput, 206 seq64::Seq24Perflirput, 579
seq64::midi_list, 380	active
~midi_splitter	seq64::midi_control, 376
- mai_opiittoi	35q0+mu_00111101, 370

add	seq64::user_midi_bus_t, 781
seq64::editable_events, 133, 134	align_selection
seq64::event_list, 159	seq64::seqroll, 672
seq64::triggers, 762	all_notes_off
add_bus	seq64::perform, 508
seq64::user_settings, 790	allow_mod4_mode
add_chord	seq64::rc_settings, 564, 566
seq64::seqroll, 662	allow_snap_split
seq64::sequence, 730	seq64::rc_settings, 564, 567
add_event	allow_two_perfedits
seq64::midi_container, 372	seq64::user_settings, 796, 800
seq64::sequence, 714, 730	analyze
add_extended_keys_page	seq64::editable_event, 125
seq64::options, 429	any_group_unmutes
add_instrument	seq64::perform, 504
seq64::user_settings, 790	any_selected_notes
add_jack_sync_page	seq64::event_list, 163
seq64::options, 429	seq64::sequence, 701
add_keyboard_page	append_sysex
seq64::options, 428	seq64::event, 148
add_long	apply_length
seq64::midi_container, 371	seq64::seqedit, 604
add_midi_clock_page	apply_song_transpose
seq64::options, 428	seq64::mainwnd, 345
add_midi_input_page	seq64::perform, 484
seq64::options, 428	seq64::sequence, 707
add_mouse_page	armed_saved
seq64::options, 429	seq64::perform, 486
add_note	at_bpm_dn
seq64::seqroll, 662	seq64::keys_perform, 293
seq64::sequence, 729	at_bpm_up
add_sequence	seq64::keys_perform, 293
seq64::perform, 480	at_event_edit
add_short	seq64::keys_perform, 296
seq64::midi_container, 372	at_fast_forward
add_trigger	seq64::keys_perform, 295
seq64::midifile, 412	at_follow_transport
seq64::sequence, 714	seq64::keys_perform, 295
add_variable	at_group_learn
seq64::midi_container, 371	seq64::keys_perform, 294
adding	at_group_off
seq64::seqroll, 675	seq64::keys_perform, 294
adj_callback_bpm	at_group_on
seq64::mainwnd, 343	seq64::keys_perform, 294
adj_callback_ss	at_keep_queue
seq64::mainwnd, 342	seq64::keys_perform, 293
adjust_offset	at_menu_mode
seq64::sequence, 744	seq64::keys_perform, 295
seq64::triggers, 770	at_pattern_edit
adjust_offsets_to_length	seq64::keys_perform, 296
seq64::triggers, 762	at_pause
adjust_timestamp	seq64::keys_perform, 295
seq64::sequence, 727	at_pointer_position
adjust_trigger_offsets_to_length	seq64::keys_perform, 296
seq64::sequence, 744	at_queue
adjustment_dummy	seq64::keys_perform, 293
seq64, 83	at_replace
alias	seq64::keys_perform, 293

at_rewind	seq64::gui_palette_gtk2, 240
seq64::keys_perform, 295	bpm_dn
at_screenset_dn	seq64::keys_perform, 282, 283
seq64::keys_perform, 294	bpm_up
at_screenset_up	seq64::keys_perform, 282
seq64::keys_perform, 294	build_details
at_set_playing_screenset	seq64, <mark>73</mark>
seq64::keys_perform, 294	build_info_dialog
at show ui sequence key	seq64::mainwnd, 346
seq64::keys_perform, 296	bus
at_show_ui_sequence_number	seq64::user_settings, 791
seq64::keys_perform, 296	bus count
at_snapshot_1	seq64::user_settings, 791
seq64::keys_perform, 294	bus instrument
at_snapshot_2	seq64::user_settings, 791
seq64::keys_perform, 294	bus_name
at_song_mode	seq64::user settings, 791
seq64::keys_perform, 295	BussConstIterator
at_start	seq64::user_settings, 789
seq64::keys perform, 295	BussIterator
at_stop	seq64::user_settings, 789
seq64::keys_perform, 296	bussbyte
at_tap_bpm	seq64, 53
seq64::keys_perform, 296	Busses 700
at_toggle_jack	seq64::user_settings, 789
seq64::keys_perform, 295	button
at_toggle_mutes	seq64::click, 109
seq64::keys_perform, 296	seq64::options, 426
auto_option_save	button_press
seq64::rc_settings, 563, 566	seq64::seqroll, 673
automutex	button_press_initial
seq64::automutex, 105	seq64::seqroll, 672
hadron day	button_release
background_sequence	seq64::seqroll, 673
seq64::sequence, 742	
baseline_ppqn	c_backsequence
seq64::user_settings, 800	seq64, 90
beat_width	c_bpmtag
seq64::midi_timing, 390	seq64, 89
beats	c_chord_number
seq64::midi_measures, 383	seq64, 94
beats_per_measure	c_chord_size
seq64::midi_timing, 390	seq64, <mark>94</mark>
beats_per_minute	c_chord_table
seq64::midi_timing, 390	seq64, <mark>94</mark>
beats_per_minute_from_tempo_us	c_chord_table_text
seq64, 66	seq64, <mark>94</mark>
begin	c_chord_text
seq64::editable_events, 133	seq64, 94
seq64::event_list, 159	c_controller_names
bg_color	seq64, <mark>84</mark>
seq64::gui_palette_gtk2, 240, 241	c_interval_text
black	seq64, 94
seq64::gui_palette_gtk2, 238	c_key_text
black_key	seq64, 94
seq64::gui_palette_gtk2, 240	c_mainwid_x
black_paint	seq64, 99
seq64::gui_palette_gtk2, 240	c_mainwid_y
blue	seq64, 99
5.55	00401,00

c_max_busses	c_scales_text
seq64, 95	seq64, <mark>93</mark>
c_max_instruments	c_scales_transpose_dn
seq64, 94	seq64, 93
c_midi_control_bpm_dn	c_scales_transpose_up
seq64, 91	seq64, 92
c_midi_control_bpm_up	c_status_queue
seq64, 91	seq64, 98
c_midi_control_mod_glearn	c_status_replace
seq64, 91	seq64, 98
c_midi_control_mod_gmute	c_status_snapshot
seq64, 91	seq64, 98
c_midi_control_mod_queue	c_timesig
seq64, 91	
·	seq64, 89
c_midi_control_mod_replace	c_transpose
seq64, 91	seq64, 90
c_midi_control_mod_snapshot	c_triggers
seq64, 91	seq64, 89
c_midi_control_play_ss	c_triggers_new
seq64, 92	seq64, 90
c_midi_control_ss_dn	calculate_base_sizes
seq64, 91	seq64::mainwid, 330
c_midi_control_ss_up	category
seq64, 91	seq64::editable_event, 122, 123
c_midi_controls	category_string
seq64, 92	seq64::editable_event, 123
c_midi_track_ctrl	category_t
seq64, 90	seq64::editable_event, 119
c midibus	change_event_data_lfo
_ seq64, 88	seq64::sequence, 732
c_midibus_input_size	change_event_data_range
seq64, 88	seq64::sequence, 732
c_midibus_output_size	change_focus
seq64, 88	seq64::eventedit, 173
c_midibus_sysex_chunk	seq64::seqedit, 609
seq64, 88	change_horz
c midich	seq64::perfroll, 539
-	seq64::perftime, 553
seq64, 89	• •
c_midiclocks	seq64::seqdata, 588
seq64, 89	seq64::seqevent, 629
c_midictrl	seq64::seqroll, 670
seq64, 90	seq64::seqtime, 688
c_music_scales	change_vert
seq64, 56	seq64::eventslots, 191
c_musickey	seq64::perfnames, 455
seq64, 90	seq64::perfroll, 539
c_musicscale	seq64::seqkeys, 641
seq64, 90	seq64::seqroll, 670
c_mutegroups	channel_count
seq64, 90	seq64::user_midi_bus, 779
c_notes	channel_match
_ seq64, 89	seq64::sequence, 745
c_perf_bp_mes	channel_max
seq64, 90	seq64::user_midi_bus, 779
c_perf_bw	channel_string
seq64, 90	seq64::editable_event, 125
c_scales_policy	char_height
seq64, 92	seq64::font, 200
3040 i, 8 2	50q5 1OIII, 200

alean and alle	
char_width	seq64::mastermidibus, 359
seq64::font, 199	seq64::midibus, 400
CharList	clock_callback_mod
seq64::midi_list, 380	seq64::options, 427
CharVector	clock_callback_off
seq64::midi_vector, 393	seq64::options, 427
check_channel	clock_callback_on
seq64::event, 142	seq64::options, 427
check_queued_tick	clock_e
seq64::sequence, 710	seq64, <mark>56</mark>
checklen	clock_mod_callback
seq64::midifile, 412	seq64::options, 427
choose_file	clock_tick_duration_bogus
seq64::mainwnd, 348	seq64, 69
choose_ppqn	clock_ticks_from_ppqn
seq64, 81	seq64, 69
clamp	clocks_per_metronome
seq64, 83, 84	seq64::perform, 474
clamp_track	• •
• —	seq64::sequence, 706
seq64::perform, 514	close_out
clear	seq64::eventedit, 174
seq64::editable_events, 134	collapse
seq64::event_list, 160	seq64::perfedit, 443
seq64::midi_container, 371	seq64::perform, 501
seq64::midi_list, 381	Color
seq64::midi_vector, 394	seq64::font, 198
seq64::triggers, 769	seq64::gui_palette_gtk2, 237
clear_all	combine_bytes
seq64::perform, 479	seq64::perform, 477
clear_flags	complete_paste
seq64::seqroll, 674	seq64::seqroll, 665, 666
clear_link	condition_var
seq64::event, 149	seq64::condition_var, 111
clear links	config_directory
seq64::event_list, 162	seq64::rc_settings, 566, 569
clear_old	config_filename
seg64::segroll, 674	seq64::rc_settings, 566, 570
clear_selected	config_filename_alt
seq64::seqroll, 674	seq64::rc_settings, 566, 570
clear_sequence_triggers	config_filespec
seq64::perform, 481	seq64::rc_settings, 563
clear_triggers	configfile
seq64::sequence, 721	seq64::configfile, 113
clear window	
-	const_iterator
seq64::gui_drawingarea_gtk2, 221	seq64::editable_events, 131
click	seq64::event_list, 158
seq64::click, 107	continue_from
client	seq64::mastermidibus, 360
seq64::jack_assistant, 259	seq64::midibus, 400
client_name	control_height
seq64::jack_assistant, 259	seq64::user_settings, 795, 799
client_open	controller_active
seq64::jack_assistant, 260	seq64::user_instrument, 775
client_uuid	seq64::user_settings, 792
seq64::jack_assistant, 259	controller_count
clip_timestamp	seq64::user_instrument, 774
seq64::sequence, 728	controller_max
clock	seq64::user_instrument, 774

controller_name	seq64::seqedit, 607
seq64::user_instrument, 774	current_event
seq64::user_settings, 792	seq64::editable_events, 134, 135
controllers	current_index
seq64::user_instrument_t, 777	seq64::eventslots, 184
controllers_active	current_screen_set_notepad
seq64::user_instrument_t, 777	seq64::perform, 503
convert_drop_xy	current_seq
seq64::perfroll, 539	seq64::seqmenu, 649
convert_sel_box_to_rect	current_x
seq64::seqroll, 669	seq64::gui_drawingarea_gtk2, 220
convert_t	current_y
seq64::seqevent, 629	seq64::gui_drawingarea_gtk2, 220
convert_tn	cut_selected
seq64::seqroll, 667	seq64::sequence, 725
convert_tn_box_to_rect	cut_selected_trigger
seq64::seqroll, 668	seq64::sequence, 718
convert_x	dark_blue
seq64::perfroll, 538	seq64::gui_palette_gtk2, 239
seq64::seqdata, 588	dark_cyan
seq64::seqevent, 629	seq64::gui_palette_gtk2, 239
convert_xy	dark green
seq64::perfroll, 537	seq64::gui_palette_gtk2, 239
seq64::seqroll, 667	dark_grey
convert_y	seq64::gui_palette_gtk2, 239
seq64::eventslots, 190	dark_magenta
seq64::perfnames, 454	seq64::gui_palette_gtk2, 239
seq64::seqkeys, 640	dark_orange
copy	seq64::gui_palette_gtk2, 239
seq64::perfedit, 444	dark_red
seq64::perform, 501	seq64::gui_palette_gtk2, 239
seq64::triggers, 768	data
copy_definitions	seq64::event, 150
seq64::user instrument, 776	seq64::midi control, 376
seq64::user_midi_bus, 780	data string
copy_events	seq64::editable_event, 125
seg64::sequence, 742	decrement beats per minute
copy_selected	seq64::perform, 493
seg64::sequence, 725	decrement bottom
seq64::triggers, 766	seq64::eventslots, 193
copy selected trigger	decrement current
seq64::sequence, 718	seq64::eventslots, 192
copy triggers	decrement data1
seq64::perform, 498	seq64::event, 147
seq64::sequence, 720	decrement data2
count	seg64::event, 148
seq64::editable events, 133	decrement offset
seq64::event_list, 159	seq64::trigger, 755
seq64::midi_splitter, 387	decrement_screenset
count selected events	seq64::perform, 493
seq64::event_list, 164	decrement_selected
count_selected_notes	seq64::sequence, 733
seq64::event_list, 163	decrement_tick_end
create_lash_driver	
seq64, 79	seq64::trigger, 754 decrement_tick_start
create_menu_image	seq64::trigger, 754
seq64::seqedit, 609	
• •	decrement_top
create_menus	seq64::eventslots, 192

deinit	seq64::seqdata, 589
seq64::jack_assistant, 254	seq64::seqevent, 627
deinit_in	seq64::seqroll, 664
seq64::midibus, 398	draw_key
deinit_jack	seq64::seqkeys, 641
seq64::perform, 510	draw_line
del_selected_trigger	seq64::gui_drawingarea_gtk2, 221, 223-225
seq64::sequence, 718	draw_line_on_pixmap
del_trigger	seq64::gui_drawingarea_gtk2, 223
seq64::sequence, 715	draw_line_on_window
delete_current_event	seq64::seqdata, 587
seq64::eventslots, 186	draw_marker_on_sequence
delete_current_sequence	seq64::mainwid, 328
seq64::seqmenu, 651	draw_normal_rectangle_on_pixmap
delete_lash_driver	seq64::gui_drawingarea_gtk2, 229
seq64, 80	draw_pixmap_on_window
delete_sequence	seq64::mainwid, 327
seq64::perform, 481	seq64::perftime, 555
delta_time_us_to_ticks	seq64::seqdata, 589
seq64, 68	seq64::seqevent, 627
device_ignore	seq64::seqtime, 687
seq64::rc_settings, 565, 568	draw_progress
device_ignore_num	seq64::perfroll, 537
seq64::rc_settings, 565, 568	draw_progress_on_window
divisions	seq64::perftime, 553
seq64::midi_measures, 383	seq64::seqroll, 664
do_action	seq64::seqtime, 687
seq64::seqedit, 609	draw_rectangle
done	seq64::gui_drawingarea_gtk2, 226-228
seq64::midi_container, 370	draw_rectangle_on_pixmap
seq64::midi_list, 381	seq64::gui_drawingarea_gtk2, 229
seq64::midi_vector, 394	draw_selection_on_window
double_ticks_from_ppqn	seq64::seqevent, 627
seq64, 70	seq64::seqroll, 664
draw_all	draw_sequence
seq64::perfroll, 536	seq64::perfnames, 454
draw area	draw_sequence_on
seq64::seqkeys, 640	seq64::perfroll, 538
draw background	draw_sequence_on_pixmap
seq64::perftime, 553	seq64::mainwid, 329
seq64::segevent, 627	draw_sequence_pixmap_on_window
draw_background_on	seq64::mainwid, 329
seq64::perfroll, 538	draw_sequences
draw_background_on_pixmap	seq64::perfedit, 444
seq64::seqroll, 664	seq64::perfnames, 454
draw_drawable	draw_sequences_on_pixmap
seq64::gui_drawingarea_gtk2, 230	seq64::mainwid, 329
draw_drawable_row	draw_type_t
seq64::perfroll, 538	seq64, 57
draw_event	dref
seq64::eventslots, 190	seq64::editable_events, 133
draw_events	seq64::event_list, 161
seq64::eventslots, 191	drop_action
draw_events_on	seq64::seqroll, 676
seq64::seqdata, 588	drop_event
seq64::seqevent, 628	seq64::seqevent, 628
seq64::seqroll, 669	drop_x
draw_events_on_pixmap	seq64::gui_drawingarea_gtk2, 220
5.55.55	Jogogaa.a.m.ga.oa_ga.e., EEO

drop_y	EVENT_NOTE_ON
seq64::gui_drawingarea_gtk2, 221	seq64, 84
dump_midi_input	EVENT_NULL_CHANNEL
seq64::mastermidibus, 361	seq64, 87
dump_setting_summary	EVENT_PITCH_WHEEL
seq64::userfile, 813	seq64, 85
dump_summary	•
	EVENT_PROGRAM_CHANGE
seq64::user_settings, 799	seq64, 85
EVENT_AFTERTOUCH	EVENT_STATUS_BIT
	seq64, <mark>84</mark>
seq64, 84	EVENTS_ALL
EVENT_ANY	seq64, 87
seq64, 84	EVENTS_UNSELECTED
EVENT_CHANNEL_PRESSURE	seq64, 87
seq64, 85	edit_action_t
EVENT_CLEAR_CHAN_MASK	seq64, 57
seq64, 87	edit_callback_notepad
EVENT_CONTROL_CHANGE	_ ·
seq64, 85	seq64::mainwnd, 343
EVENT_GÉT_CHAN_MASK	edit_field_has_focus
seq64, 87	seq64::mainwnd, 348
EVENT_MIDI_ACTIVE_SENS	editable_event
	seq64::editable_event, 120, 121
seq64, 87	editable_events
EVENT_MIDI_CLOCK	seq64::editable_events, 131
seq64, 86	seq64::event_list, 165
EVENT_MIDI_CONTINUE	. —
seq64, 86	empty
EVENT_MIDI_META	seq64::event_list, 159
seq64, 87	end
EVENT_MIDI_QUARTER_FRAME	seq64::editable_events, 133
seq64, 85	seq64::event_list, 159
EVENT_MIDI_RESET	enqueue_draw
seq64, 87	seq64::eventedit, 171
EVENT_MIDI_SONG_F4	seq64::eventslots, 190
	seq64::perfedit, 440
seq64, 86	seg64::perfnames, 454
EVENT_MIDI_SONG_F5	seq64::perfroll, 539
seq64, 86	seq64::perftime, 552
EVENT_MIDI_SONG_F9	• •
seq64, 86	enregister
EVENT_MIDI_SONG_FD	seq64::perform, 476
seq64, 87	enregister_peer
EVENT_MIDI_SONG_POS	seq64::perfedit, 440
seq64, 85	enregister_perfedits
EVENT_MIDI_SONG_SELECT	seq64::mainwnd, 345
seq64, 85	errdump
EVENT MIDI START	seq64::midifile, 419
seq64, 86	error is fatal
EVENT_MIDI_STOP	seq64::midifile, 409
	•
seq64, 86	error_message
EVENT_MIDI_SYSEX_CONTINUE	seq64::jack_assistant, 260
seq64, 86	seq64::midifile, 409
EVENT_MIDI_SYSEX_END	seq64::optionsfile, 434
seq64, 86	event
EVENT_MIDI_SYSEX	seq64::event, 140
seq64, 85	event_count
EVENT_MIDI_TUNE_SELECT	seq64::eventslots, 184
seq64, 86	seq64::sequence, 702
EVENT_NOTE_OFF	event edit
seq64, 84	seq64::keys_perform, 287
3040 - , 0-	Joquanneys_penonii, 207

	en n
event_in_range	file_exit
seq64::sequence, 743	seq64::mainwnd, 347
event_key	file_import_dialog
seq64::event_list::event_key, 154, 155	seq64::mainwnd, 346
event_list	file_is_directory
seq64::event_list, 158	seq64, 75
event_name	file_new
seq64::editable_event::name_value_t, 425	seq64::mainwnd, 345
event_value	file_open
seq64::editable_event::name_value_t, 425	seq64::mainwnd, 345
EventStack	file readable
seq64::sequence, 700	seq64, 74
eventedit	•
seq64::eventedit, 169	file_save
seq64::eventslots, 195	seq64::mainwnd, 346
Events	file_save_as
	seq64::mainwnd, 347
seq64::editable_events, 130	file_writable
seq64::event_list, 158	seq64, 74
events	filename
seq64::editable_events, 132	seq64::rc_settings, 565, 569
seq64::event_list, 164	fill
seq64::sequence, 701	seq64::midi_container, 369
EventsPair	fill_background_pixmap
seq64::editable_events, 130	seq64::perfroll, 536
seq64::event_list, 158	fill_background_window
eventslots	seq64::mainwid, 327
seq64::editable_events, 135	•
seq64::eventedit, 176	fill_meta_track_end
seq64::eventslots, 184	seq64::midi_container, 373
expand	fill_proprietary
seq64::perfedit, 443	seq64::midi_container, 373
seq64::perform, 501	fill_seq_name
extract timing numbers	seq64::midi_container, 372
_ <u>~</u>	fill_seq_number
seq64, 58	seq64::midi_container, 372
FF_RW_timeout	fill_time_sig_and_tempo
seq64, 83	seq64::midi container, 373
• •	fill_top_bar
seq64::perfedit, 446	seq64::seqedit, 607
seq64::perform, 477	filter_by_channel
FF_rewind	seq64::mastermidibus, 358
seq64::perform, 477	seq64::perform, 475
fast_forward	
seq64::keys_perform, 288	seq64::rc_settings, 565, 567
seq64::perfedit, 441	filter_callback
seq64::perform, 479	seq64::options, 427
ff_rw_button_t	finish
seq64::perform, 471	seq64::perform, 482
ff_rw_type	flush
seq64::perform, 478	seq64::mastermidibus, 359
fg_color	seq64::midibus, 401
seq64::gui_palette_gtk2, 241	follow_progress
file access	seq64::perfroll, 536
seq64, 74	seq64::seqroll, 666
file_accessible	follow_transport
seq64, 75	seq64::keys_perform, 288
file_executable	font
seq64, 75	seq64::font, 199
file_exists	font_render
seq64, 74	seq64, 82

force_draw	get_current_sequence
seq64::gui_drawingarea_gtk2, 221	seq64::seqmenu, 650
seq64::seqevent, 627	get_data
seq64::seqkeys, 640	seq64::event, 147
seq64::seqroll, 666	get_editing
format_timestamp	seq64::sequence, 707
seq64::editable_event, 124	get_follow_transport
FruityPerfInput	seq64::jack_assistant, 258
seq64::FruityPerfInput, 203	seq64::perform, 478
seq64::perfroll, 544	get_group_mute_state
seg64::triggers, 771	
FruitySeqEventInput	seq64::perform, 488
seq64::FruitySeqEventInput, 207	get_hold_undo
seq64::seqevent, 633	seq64::sequence, 703
FruitySeqRollInput	get_id
	seq64::midibus, 399
seq64::FruitySeqRollInput, 210	get_input
seq64::seqkeys, 644	seq64::mastermidibus, 364
seq64::seqroll, 680	seq64::midibus, 401
g_rc_settings	get_jack_client_info
seq64, 98	seq64::jack_assistant, 261
•	get_jack_mode
g_user_settings	seq64::jack_assistant, 258
seq64, 98	get_jack_pos
get	seq64::jack_assistant, 257
seq64::midi_container, 370	get_jack_stop_tick
seq64::midi_list, 381	seq64::jack_assistant, 258
seq64::midi_vector, 394	get_jack_tick
get_32nds_per_quarter	seq64::jack_assistant, 257
seq64::perform, 474	seq64::perform, 482
seq64::sequence, 706	get_key_events
get_alsa_seq	seq64::keys_perform, 290
seq64::mastermidibus, 357	
get_beat_width	seq64::perform, 489
seq64::jack_assistant, 253	get_key_events_rev
seq64::perform, 474	seq64::keys_perform, 290
seq64::sequence, 705	seq64::perform, 489
get_beats_per_bar	get_key_groups
seq64::perform, 473	seq64::keys_perform, 290
seq64::sequence, 705	seq64::perform, 489
get_beats_per_measure	get_key_groups_rev
seq64::jack_assistant, 253	seq64::keys_perform, 291
get_beats_per_minute	seq64::perform, 489
seq64::jack_assistant, 253	get_keys
seq64::mastermidibus, 358	seq64::keys_perform, 282
seq64::perform, 484	get_last_tick
get_channel	seq64::sequence, 708
seq64::event, 142	get_left_tick
get_client	seq64::perform, 482
seq64::midibus, 401	get_length
get_clipboard_box	seq64::sequence, 708
seq64::sequence, 727	get_linked
·	seq64::event, 149
get_clock	get_max_trigger
seq64::mastermidibus, 363	
seq64::midibus, 401	seq64::perform, 501
get_clock_mod	seq64::sequence, 720
seq64::midibus, 402	get_maximum
get_current_jack_position	seq64::triggers, 767
seq64, 78	get_measures
seq64::perform, 519	seq64::seqedit, 604

seq64::sequence, 705	get_right_tick
get_midi_bus	seq64::perform, 483
seq64::sequence, 721	get_screen_set_notepad
get_midi_channel	seq64::perform, 503
seq64::sequence, 712	get_screenset
get_midi_event	seq64::perform, 500
seq64::mastermidibus, 360	get_selected_box
get_midi_in_bus_name	seq64::seqroll, 669
seq64::mastermidibus, 358	seq64::sequence, 726
get_midi_out_bus_name	get_selected_end
seq64::mastermidibus, 358	seq64::triggers, 767
get_minmax_note_events	get_selected_start
seq64::sequence, 739	seq64::triggers, 767
get_name	get_sequence
seq64::midibus, 399	seq64::mastermidibus, 361
seq64::sequence, 707	seq64::perform, 494
get_next_event	seq64::seqmenu, 650
seq64::sequence, 739, 740	get_song_mute
get_next_note_event	seq64::sequence, 707
seq64::sequence, 738	get_start_tick
get_next_trigger	seq64::perform, 483
seq64::sequence, 740	get_state
get_note	seq64::triggers, 764
seq64::event, 150	get_status
get_note_velocity	seq64::event, 147
seq64::event, 151	get_sysex
get_num_in_buses	seq64::event, 148, 149
seq64::mastermidibus, 357	get_sysex_size
act num out bucce	seq64::event, 149
get_num_out_buses	
seq64::mastermidibus, 357	get_thru
seq64::mastermidibus, 357 get_num_selected_events	get_thru seq64::sequence, 711
seq64::mastermidibus, 357 get_num_selected_events seq64::sequence, 724	get_thru seq64::sequence, 711 get_tick
seq64::mastermidibus, 357 get_num_selected_events seq64::sequence, 724 get_num_selected_notes	get_thru seq64::sequence, 711 get_tick seq64::perform, 482
seq64::mastermidibus, 357 get_num_selected_events seq64::sequence, 724 get_num_selected_notes seq64::sequence, 724	get_thru seq64::sequence, 711 get_tick seq64::perform, 482 get_timestamp
seq64::mastermidibus, 357 get_num_selected_events seq64::sequence, 724 get_num_selected_notes seq64::sequence, 724 get_offset	get_thru seq64::sequence, 711 get_tick seq64::perform, 482 get_timestamp seq64::event, 142
seq64::mastermidibus, 357 get_num_selected_events seq64::sequence, 724 get_num_selected_notes seq64::sequence, 724 get_offset seq64::perform, 488	get_thru seq64::sequence, 711 get_tick seq64::perform, 482 get_timestamp seq64::event, 142 get_toggle_jack
seq64::mastermidibus, 357 get_num_selected_events seq64::sequence, 724 get_num_selected_notes seq64::sequence, 724 get_offset seq64::perform, 488 get_playing	get_thru seq64::sequence, 711 get_tick seq64::perform, 482 get_timestamp seq64::event, 142 get_toggle_jack seq64::perfedit, 441
seq64::mastermidibus, 357 get_num_selected_events seq64::sequence, 724 get_num_selected_notes seq64::sequence, 724 get_offset seq64::perform, 488 get_playing seq64::sequence, 709	get_thru seq64::sequence, 711 get_tick seq64::perform, 482 get_timestamp seq64::event, 142 get_toggle_jack seq64::perfedit, 441 seq64::perform, 477
seq64::mastermidibus, 357 get_num_selected_events seq64::sequence, 724 get_num_selected_notes seq64::sequence, 724 get_offset seq64::perform, 488 get_playing seq64::sequence, 709 get_playing_screenset	get_thru seq64::sequence, 711 get_tick seq64::perform, 482 get_timestamp seq64::event, 142 get_toggle_jack seq64::perfedit, 441 seq64::perform, 477 get_transposable
seq64::mastermidibus, 357 get_num_selected_events seq64::sequence, 724 get_num_selected_notes seq64::sequence, 724 get_offset seq64::perform, 488 get_playing seq64::sequence, 709 get_playing_screenset seq64::perform, 500	get_thru seq64::sequence, 711 get_tick seq64::perform, 482 get_timestamp seq64::event, 142 get_toggle_jack seq64::perfedit, 441 seq64::perform, 477 get_transposable seq64::sequence, 707
seq64::mastermidibus, 357 get_num_selected_events seq64::sequence, 724 get_num_selected_notes seq64::sequence, 724 get_offset seq64::perform, 488 get_playing seq64::sequence, 709 get_playing_screenset seq64::perform, 500 get_port	get_thru seq64::sequence, 711 get_tick seq64::perform, 482 get_timestamp seq64::event, 142 get_toggle_jack seq64::perfedit, 441 seq64::perform, 477 get_transposable seq64::sequence, 707 get_transpose
seq64::mastermidibus, 357 get_num_selected_events seq64::sequence, 724 get_num_selected_notes seq64::sequence, 724 get_offset seq64::perform, 488 get_playing seq64::sequence, 709 get_playing_screenset seq64::perform, 500 get_port seq64::midibus, 401	get_thru seq64::sequence, 711 get_tick seq64::perform, 482 get_timestamp seq64::event, 142 get_toggle_jack seq64::perfedit, 441 seq64::perform, 477 get_transposable seq64::sequence, 707 get_transpose seq64::perform, 484
seq64::mastermidibus, 357 get_num_selected_events seq64::sequence, 724 get_num_selected_notes seq64::sequence, 724 get_offset seq64::perform, 488 get_playing seq64::sequence, 709 get_playing_screenset seq64::perform, 500 get_port seq64::midibus, 401 get_ppqn	get_thru seq64::sequence, 711 get_tick seq64::perform, 482 get_timestamp seq64::event, 142 get_toggle_jack seq64::perfedit, 441 seq64::perform, 477 get_transposable seq64::sequence, 707 get_transpose seq64::perform, 484 get_trigger_count
seq64::mastermidibus, 357 get_num_selected_events seq64::sequence, 724 get_num_selected_notes seq64::sequence, 724 get_offset seq64::perform, 488 get_playing seq64::sequence, 709 get_playing_screenset seq64::perform, 500 get_port seq64::midibus, 401 get_ppqn seq64::jack_assistant, 252	get_thru seq64::sequence, 711 get_tick seq64::perform, 482 get_timestamp seq64::event, 142 get_toggle_jack seq64::perfedit, 441 seq64::perform, 477 get_transposable seq64::sequence, 707 get_transpose seq64::perform, 484 get_trigger_count seq64::sequence, 702
seq64::mastermidibus, 357 get_num_selected_events seq64::sequence, 724 get_num_selected_notes seq64::sequence, 724 get_offset seq64::perform, 488 get_playing seq64::sequence, 709 get_playing_screenset seq64::perform, 500 get_port seq64::midibus, 401 get_ppqn seq64::jack_assistant, 252 seq64::mastermidibus, 358	get_thru seq64::sequence, 711 get_tick seq64::perform, 482 get_timestamp seq64::event, 142 get_toggle_jack seq64::perfedit, 441 seq64::perform, 477 get_transposable seq64::sequence, 707 get_transpose seq64::perform, 484 get_trigger_count seq64::sequence, 702 get_trigger_offset
seq64::mastermidibus, 357 get_num_selected_events seq64::sequence, 724 get_num_selected_notes seq64::sequence, 724 get_offset seq64::perform, 488 get_playing seq64::sequence, 709 get_playing_screenset seq64::perform, 500 get_port seq64::midibus, 401 get_ppqn seq64::jack_assistant, 252 seq64::mastermidibus, 358 seq64::sequence, 705	get_thru seq64::sequence, 711 get_tick seq64::perform, 482 get_timestamp seq64::event, 142 get_toggle_jack seq64::perfedit, 441 seq64::perform, 477 get_transposable seq64::sequence, 707 get_transpose seq64::perform, 484 get_trigger_count seq64::sequence, 702 get_trigger_offset seq64::sequence, 721
seq64::mastermidibus, 357 get_num_selected_events seq64::sequence, 724 get_num_selected_notes seq64::sequence, 724 get_offset seq64::perform, 488 get_playing seq64::sequence, 709 get_playing_screenset seq64::perform, 500 get_port seq64::midibus, 401 get_ppqn seq64::jack_assistant, 252 seq64::mastermidibus, 358 seq64::sequence, 705 get_quantized_rec	get_thru seq64::sequence, 711 get_tick seq64::perform, 482 get_timestamp seq64::event, 142 get_toggle_jack seq64::perfedit, 441 seq64::perform, 477 get_transposable seq64::sequence, 707 get_transpose seq64::perform, 484 get_trigger_count seq64::sequence, 702 get_trigger_offset seq64::sequence, 721 get_trigger_paste_tick
seq64::mastermidibus, 357 get_num_selected_events seq64::sequence, 724 get_num_selected_notes seq64::sequence, 724 get_offset seq64::perform, 488 get_playing seq64::sequence, 709 get_playing_screenset seq64::perform, 500 get_port seq64::midibus, 401 get_ppqn seq64::jack_assistant, 252 seq64::mastermidibus, 358 seq64::sequence, 705 get_quantized_rec seq64::sequence, 711	get_thru seq64::sequence, 711 get_tick seq64::perform, 482 get_timestamp seq64::event, 142 get_toggle_jack seq64::perfedit, 441 seq64::perform, 477 get_transposable seq64::sequence, 707 get_transpose seq64::perform, 484 get_trigger_count seq64::sequence, 702 get_trigger_offset seq64::sequence, 721 get_trigger_paste_tick seq64::sequence, 702
seq64::mastermidibus, 357 get_num_selected_events seq64::sequence, 724 get_num_selected_notes seq64::sequence, 724 get_offset seq64::perform, 488 get_playing seq64::sequence, 709 get_playing_screenset seq64::perform, 500 get_port seq64::midibus, 401 get_ppqn seq64::jack_assistant, 252 seq64::mastermidibus, 358 seq64::sequence, 705 get_quantized_rec seq64::sequence, 711 get_queued	get_thru seq64::sequence, 711 get_tick seq64::perform, 482 get_timestamp seq64::event, 142 get_toggle_jack seq64::perfedit, 441 seq64::perform, 477 get_transposable seq64::sequence, 707 get_transpose seq64::perform, 484 get_trigger_count seq64::sequence, 702 get_trigger_offset seq64::sequence, 721 get_trigger_paste_tick seq64::sequence, 702 seq64::sequence, 702 seq64::riggers, 770
seq64::mastermidibus, 357 get_num_selected_events seq64::sequence, 724 get_num_selected_notes seq64::sequence, 724 get_offset seq64::perform, 488 get_playing seq64::sequence, 709 get_playing_screenset seq64::perform, 500 get_port seq64::midibus, 401 get_ppqn seq64::jack_assistant, 252 seq64::mastermidibus, 358 seq64::sequence, 705 get_quantized_rec seq64::sequence, 711 get_queued seq64::sequence, 710	get_thru seq64::sequence, 711 get_tick seq64::perform, 482 get_timestamp seq64::event, 142 get_toggle_jack seq64::perfedit, 441 seq64::perform, 477 get_transposable seq64::sequence, 707 get_transpose seq64::perform, 484 get_trigger_count seq64::sequence, 702 get_trigger_offset seq64::sequence, 721 get_trigger_paste_tick seq64::sequence, 702 seq64::triggers, 770 get_trigger_state
seq64::mastermidibus, 357 get_num_selected_events seq64::sequence, 724 get_num_selected_notes seq64::sequence, 724 get_offset seq64::perform, 488 get_playing seq64::sequence, 709 get_playing_screenset seq64::perform, 500 get_port seq64::midibus, 401 get_ppqn seq64::jack_assistant, 252 seq64::mastermidibus, 358 seq64::sequence, 705 get_quantized_rec seq64::sequence, 711 get_queued seq64::sequence, 710 get_queued_tick	get_thru seq64::sequence, 711 get_tick seq64::perform, 482 get_timestamp seq64::event, 142 get_toggle_jack seq64::perfedit, 441 seq64::perform, 477 get_transposable seq64::sequence, 707 get_transpose seq64::perform, 484 get_trigger_count seq64::sequence, 702 get_trigger_offset seq64::sequence, 721 get_trigger_paste_tick seq64::sequence, 702 seq64::triggers, 770 get_trigger_state seq64::sequence, 716
seq64::mastermidibus, 357 get_num_selected_events seq64::sequence, 724 get_num_selected_notes seq64::sequence, 724 get_offset seq64::perform, 488 get_playing seq64::sequence, 709 get_playing_screenset seq64::perform, 500 get_port seq64::midibus, 401 get_ppqn seq64::jack_assistant, 252 seq64::mastermidibus, 358 seq64::sequence, 705 get_quantized_rec seq64::sequence, 711 get_queued seq64::sequence, 710 get_queued_tick seq64::sequence, 710	get_thru seq64::sequence, 711 get_tick seq64::perform, 482 get_timestamp seq64::event, 142 get_toggle_jack seq64::perform, 477 get_transposable seq64::sequence, 707 get_transpose seq64::perform, 484 get_trigger_count seq64::sequence, 702 get_trigger_offset seq64::sequence, 721 get_trigger_paste_tick seq64::sequence, 702 seq64::triggers, 770 get_trigger_state seq64::sequence, 716 get_triggers
seq64::mastermidibus, 357 get_num_selected_events seq64::sequence, 724 get_num_selected_notes seq64::sequence, 724 get_offset seq64::perform, 488 get_playing seq64::sequence, 709 get_playing_screenset seq64::perform, 500 get_port seq64::midibus, 401 get_ppqn seq64::jack_assistant, 252 seq64::mastermidibus, 358 seq64::sequence, 705 get_quantized_rec seq64::sequence, 711 get_queued seq64::sequence, 710 get_queued_tick seq64::sequence, 710 get_raise	get_thru seq64::sequence, 711 get_tick seq64::perform, 482 get_timestamp seq64::event, 142 get_toggle_jack seq64::perform, 477 get_transposable seq64::sequence, 707 get_transpose seq64::perform, 484 get_trigger_count seq64::sequence, 702 get_trigger_offset seq64::sequence, 721 get_trigger_paste_tick seq64::sequence, 702 seq64::sequence, 702 seq64::sequence, 702 seq64::sequence, 702 seq64::sequence, 706 get_trigger_state seq64::sequence, 716 get_triggers seq64::sequence, 716
seq64::mastermidibus, 357 get_num_selected_events seq64::sequence, 724 get_num_selected_notes seq64::sequence, 724 get_offset seq64::perform, 488 get_playing seq64::sequence, 709 get_playing_screenset seq64::perform, 500 get_port seq64::midibus, 401 get_ppqn seq64::jack_assistant, 252 seq64::mastermidibus, 358 seq64::sequence, 705 get_quantized_rec seq64::sequence, 711 get_queued seq64::sequence, 710 get_queued_tick seq64::sequence, 710 get_raise seq64::sequence, 708	get_thru seq64::sequence, 711 get_tick seq64::perform, 482 get_timestamp seq64::event, 142 get_toggle_jack seq64::perfedit, 441 seq64::perform, 477 get_transposable seq64::sequence, 707 get_transpose seq64::perform, 484 get_trigger_count seq64::sequence, 702 get_trigger_offset seq64::sequence, 721 get_trigger_paste_tick seq64::sequence, 702 seq64::triggers, 770 get_trigger_state seq64::sequence, 716 get_triggers seq64::sequence, 716 get_triggers seq64::sequence, 716 global_seq_feature
seq64::mastermidibus, 357 get_num_selected_events seq64::sequence, 724 get_num_selected_notes seq64::sequence, 724 get_offset seq64::perform, 488 get_playing seq64::sequence, 709 get_playing_screenset seq64::perform, 500 get_port seq64::midibus, 401 get_ppqn seq64::jack_assistant, 252 seq64::mastermidibus, 358 seq64::sequence, 705 get_quantized_rec seq64::sequence, 711 get_queued seq64::sequence, 710 get_queued_tick seq64::sequence, 710 get_raise seq64::sequence, 708 get_rank	get_thru seq64::sequence, 711 get_tick seq64::perform, 482 get_timestamp seq64::event, 142 get_toggle_jack seq64::perfedit, 441 seq64::perform, 477 get_transposable seq64::sequence, 707 get_transpose seq64::perform, 484 get_trigger_count seq64::sequence, 702 get_trigger_offset seq64::sequence, 721 get_trigger_paste_tick seq64::sequence, 702 seq64::triggers, 770 get_trigger_state seq64::sequence, 716 get_triggers seq64::sequence, 716 global_seq_feature seq64::user_settings, 795
seq64::mastermidibus, 357 get_num_selected_events seq64::sequence, 724 get_num_selected_notes seq64::sequence, 724 get_offset seq64::perform, 488 get_playing seq64::sequence, 709 get_playing_screenset seq64::perform, 500 get_port seq64::midibus, 401 get_ppqn seq64::jack_assistant, 252 seq64::mastermidibus, 358 seq64::sequence, 705 get_quantized_rec seq64::sequence, 711 get_queued seq64::sequence, 710 get_queued_tick seq64::sequence, 710 get_raise seq64::sequence, 708 get_rank seq64::event, 152	get_thru seq64::sequence, 711 get_tick seq64::perform, 482 get_timestamp seq64::event, 142 get_toggle_jack seq64::perfedit, 441 seq64::perform, 477 get_transposable seq64::sequence, 707 get_transpose seq64::perform, 484 get_trigger_count seq64::sequence, 702 get_trigger_offset seq64::sequence, 721 get_trigger_paste_tick seq64::sequence, 702 seq64::triggers, 770 get_trigger_state seq64::sequence, 716 get_triggers seq64::sequence, 716 get_triggers seq64::sequence, 716 get_triggers seq64::sequence, 716 get_triggers seq64::sequence, 716 global_seq_feature seq64::user_settings, 795 gmute_tracks
seq64::mastermidibus, 357 get_num_selected_events seq64::sequence, 724 get_num_selected_notes seq64::sequence, 724 get_offset seq64::perform, 488 get_playing seq64::sequence, 709 get_playing_screenset seq64::perform, 500 get_port seq64::midibus, 401 get_ppqn seq64::jack_assistant, 252 seq64::mastermidibus, 358 seq64::sequence, 705 get_quantized_rec seq64::sequence, 711 get_queued seq64::sequence, 710 get_queued_tick seq64::sequence, 710 get_raise seq64::sequence, 708 get_rank	get_thru seq64::sequence, 711 get_tick seq64::perform, 482 get_timestamp seq64::event, 142 get_toggle_jack seq64::perfedit, 441 seq64::perform, 477 get_transposable seq64::sequence, 707 get_transpose seq64::perform, 484 get_trigger_count seq64::sequence, 702 get_trigger_offset seq64::sequence, 721 get_trigger_paste_tick seq64::sequence, 702 seq64::triggers, 770 get_trigger_state seq64::sequence, 716 get_triggers seq64::sequence, 716 global_seq_feature seq64::user_settings, 795

seq64::gui_palette_gtk2, 240	handle_config
grey	seq64::lash, 313
seq64::gui_palette_gtk2, 239	handle_delete
grid_brackets	seq64::eventedit, 174
seq64::user_settings, 793, 797	handle_event
grid_is_black	seq64::lash, 312
seq64::user_settings, 793	handle_insert
grid_is_normal	seq64::eventedit, 174
seq64::user_settings, 793	handle_midi_control
grid_is_white	seq64::perform, 502
seq64::user_settings, 793	handle_modify
grid_style	seq64::eventedit, 174
seq64::user_settings, 792, 797	handle_motion_key
group_learn	seq64::AbstractPerfInput, 103
seq64::keys_perform, 286	seq64::FruityPerfInput, 206
group_off	seq64::Seq24PerfInput, 579
seq64::keys_perform, 286	handle_save
group_on	seq64::eventedit, 174
seq64::keys_perform, 285	handle_signal
grow	seq64::mainwnd, 342
seq64::perfedit, 443	have_redo
seq64::triggers, 763	seq64::perform, 501
grow_edit_t	seq64::sequence, 703
seq64::triggers, 759	have_undo
grow_selected	seq64::perform, 500
seq64::sequence, 735	seq64::sequence, 703
grow_selected_notes	height
seq64::seqroll, 672	seq64::gui_drawingarea_gtk2::rect, 576
grow_trigger	seq64::rect, 575
seq64::sequence, 715	help_check
growing	seq64, 71
seq64::seqroll, 675	seq64::rc_settings, 572
gs_mainwid_pointer	highlight
seq64, 99	seq64::perform, 494
gs_perfedit_pointer_0	home_config_directory
seq64, 99	seq64::rc_settings, 570
gs_perfedit_pointer_1	horizontal_adjust
seq64, 99	seq64::perfroll, 540
Gtk, 41	seq64::seqedit, 603
gtk_drawarea_init	seq64::seqroll, 666
seq64::gui_drawingarea_gtk2, 231	horizontal_set
gui	seq64::perfroll, 541
seq64::perform, 475	seq64::seqedit, 603
gui_assistant	4 4 5
seq64::gui_assistant, 213	idle_progress
gui_assistant_gtk2	seq64::maintime, 320
seq64::gui assistant gtk2, 215	seq64::perftime, 554
gui_drawingarea_gtk2	seq64::seqroll, 669
seq64::gui_drawingarea_gtk2, 219, 220	seq64::seqtime, 688
gui_palette_gtk2	idle_redraw
seq64::gui_palette_gtk2, 238	seq64::seqdata, 587
gui_window_gtk2	seq64::seqevent, 627
seq64::gui_window_gtk2, 245	seq64::seqroll, 669
Jogotgui_wiiidow_ginz, 270	in_range
handle_cancel	seq64::midi_control, 377
seq64::eventedit, 174	increment
handle_close	seq64::midi_splitter, 386
seq64::eventedit, 174	increment_beats_per_minute
seq64::seqedit, 610	seq64::perform, 493
· · · · · · · · · · · · · · · · · · ·	the state of the s

increment_bottom	seq64::perform, 516
seq64::eventslots, 193	insert_event
increment_current	seq64::eventslots, 185, 186
seq64::eventslots, 192	install_sequence
increment data1	seq64::perform, 513
seq64::event, 147	install_signal_handlers
increment_data2	seq64::mainwnd, 348
seq64::event, 148	instrument
increment_offset	seq64::user_instrument_t, 777
seq64::trigger, 755	seq64::user_midi_bus, 779
increment_screenset	seq64::user_midi_bus_t, 781
seq64::perform, 494	seq64::user_settings, 791
increment_selected	instrument_controller_active
seq64::sequence, 733	seq64::user_settings, 792
increment size	instrument_controller_name
seq64::perfroll, 536	seq64::user_settings, 792
seq64::perftime, 552	
increment tick end	instrument_count
	seq64::user_settings, 791
seq64::trigger, 754	instrument_name
increment_tick_start	seq64::user_settings, 792
seq64::trigger, 754	InstrumentConstIterator
increment_top	seq64::user_settings, 789
seq64::eventslots, 192	InstrumentIterator
info_message	seq64::user_settings, 789
seq64::jack_assistant, 259	Instruments
init	seq64::user_settings, 789
seq64::font, 199	interaction_method
seq64::jack_assistant, 254	seq64::rc_settings, 565, 568
seq64::lash, 312	interaction_method_t
seq64::mastermidibus, 357	seq64, <mark>56</mark>
init_before_show	intersect
seq64::perfedit, 440	seq64::triggers, 764
seq64::perfroll, 536	intersect_events
seq64::perfroll, 536 init_clock	intersect_events seq64::sequence, 718
init_clock seq64::mastermidibus, 360	
init_clock	seq64::sequence, 718
init_clock seq64::mastermidibus, 360	seq64::sequence, 718 intersect_notes
init_clock seq64::mastermidibus, 360 seq64::midibus, 400	seq64::sequence, 718 intersect_notes seq64::sequence, 717
init_clock seq64::mastermidibus, 360 seq64::midibus, 400 init_in	seq64::sequence, 718 intersect_notes seq64::sequence, 717 intersect_triggers
init_clock seq64::mastermidibus, 360 seq64::midibus, 400 init_in seq64::midibus, 398	seq64::sequence, 718 intersect_notes seq64::sequence, 717 intersect_triggers seq64::sequence, 717
init_clock seq64::mastermidibus, 360 seq64::midibus, 400 init_in seq64::midibus, 398 init_in_sub	seq64::sequence, 718 intersect_notes seq64::sequence, 717 intersect_triggers seq64::sequence, 717 invalid_key
init_clock seq64::mastermidibus, 360 seq64::midibus, 400 init_in seq64::midibus, 398 init_in_sub seq64::midibus, 399	seq64::sequence, 718 intersect_notes seq64::sequence, 717 intersect_triggers seq64::sequence, 717 invalid_key seq64, 79
init_clock seq64::mastermidibus, 360 seq64::midibus, 400 init_in seq64::midibus, 398 init_in_sub seq64::midibus, 399 init_jack	seq64::sequence, 718 intersect_notes seq64::sequence, 717 intersect_triggers seq64::sequence, 717 invalid_key seq64, 79 inverse_active
init_clock seq64::mastermidibus, 360 seq64::midibus, 400 init_in seq64::midibus, 398 init_in_sub seq64::midibus, 399 init_jack seq64::perform, 510	seq64::sequence, 718 intersect_notes seq64::sequence, 717 intersect_triggers seq64::sequence, 717 invalid_key seq64, 79 inverse_active seq64::midi_control, 376
init_clock seq64::mastermidibus, 360 seq64::midibus, 400 init_in seq64::midibus, 398 init_in_sub seq64::midibus, 399 init_jack seq64::perform, 510 init_out	seq64::sequence, 718 intersect_notes seq64::sequence, 717 intersect_triggers seq64::sequence, 717 invalid_key seq64, 79 inverse_active seq64::midi_control, 376 inverse_colors
init_clock seq64::mastermidibus, 360 seq64::midibus, 400 init_in seq64::midibus, 398 init_in_sub seq64::midibus, 399 init_jack seq64::perform, 510 init_out seq64::midibus, 398	seq64::sequence, 718 intersect_notes seq64::sequence, 717 intersect_triggers seq64::sequence, 717 invalid_key seq64, 79 inverse_active seq64::midi_control, 376 inverse_colors seq64::user_settings, 797, 801
init_clock seq64::mastermidibus, 360 seq64::midibus, 400 init_in seq64::midibus, 398 init_in_sub seq64::midibus, 399 init_jack seq64::perform, 510 init_out seq64::midibus, 398 init_out_sub	seq64::sequence, 718 intersect_notes seq64::sequence, 717 intersect_triggers seq64::sequence, 717 invalid_key seq64, 79 inverse_active seq64::midi_control, 376 inverse_colors seq64::user_settings, 797, 801 is
init_clock seq64::mastermidibus, 360 seq64::midibus, 400 init_in seq64::midibus, 398 init_in_sub seq64::midibus, 399 init_jack seq64::perform, 510 init_out seq64::midibus, 398 init_out_sub seq64::midibus, 398 init_out_sub seq64::midibus, 398 initialize	seq64::sequence, 718 intersect_notes seq64::sequence, 717 intersect_triggers seq64::sequence, 717 invalid_key seq64, 79 inverse_active seq64::midi_control, 376 inverse_colors seq64::user_settings, 797, 801 is seq64::keystroke, 309 is_active
init_clock seq64::mastermidibus, 360 seq64::midibus, 400 init_in seq64::midibus, 398 init_in_sub seq64::midibus, 399 init_jack seq64::perform, 510 init_out seq64::midibus, 398 init_out_sub seq64::midibus, 398 init_out_sub seq64::midibus, 398 initialize seq64::midi_splitter, 386	seq64::sequence, 718 intersect_notes seq64::sequence, 717 intersect_triggers seq64::sequence, 717 invalid_key seq64, 79 inverse_active seq64::midi_control, 376 inverse_colors seq64::user_settings, 797, 801 is seq64::keystroke, 309 is_active seq64::perform, 483
init_clock seq64::mastermidibus, 360 seq64::midibus, 400 init_in seq64::midibus, 398 init_in_sub seq64::midibus, 399 init_jack seq64::perform, 510 init_out seq64::midibus, 398 init_out_sub seq64::midibus, 398 init_out_sub seq64::midibus, 398 initalize seq64::midi_splitter, 386 inner_start	seq64::sequence, 718 intersect_notes seq64::sequence, 717 intersect_triggers seq64::sequence, 717 invalid_key seq64, 79 inverse_active seq64::midi_control, 376 inverse_colors seq64::user_settings, 797, 801 is seq64::keystroke, 309 is_active seq64::perform, 483 is_adding
init_clock seq64::mastermidibus, 360 seq64::midibus, 400 init_in seq64::midibus, 398 init_in_sub seq64::midibus, 399 init_jack seq64::perform, 510 init_out seq64::midibus, 398 init_out_sub seq64::midibus, 398 init_out_sub seq64::midibus, 398 initalize seq64::midi_splitter, 386 inner_start seq64::perform, 514	seq64::sequence, 718 intersect_notes seq64::sequence, 717 intersect_triggers seq64::sequence, 717 invalid_key seq64, 79 inverse_active seq64::midi_control, 376 inverse_colors seq64::user_settings, 797, 801 is seq64::keystroke, 309 is_active seq64::perform, 483 is_adding seq64::AbstractPerfInput, 103
init_clock seq64::mastermidibus, 360 seq64::midibus, 400 init_in seq64::midibus, 398 init_in_sub seq64::midibus, 399 init_jack seq64::perform, 510 init_out seq64::midibus, 398 init_out_sub seq64::midibus, 398 initialize seq64::midi_splitter, 386 inner_start seq64::perform, 514 inner_stop	seq64::sequence, 718 intersect_notes seq64::sequence, 717 intersect_triggers seq64::sequence, 717 invalid_key seq64, 79 inverse_active seq64::midi_control, 376 inverse_colors seq64::user_settings, 797, 801 is seq64::keystroke, 309 is_active seq64::perform, 483 is_adding seq64::AbstractPerfInput, 103 is_adding_pressed
init_clock seq64::mastermidibus, 360 seq64::midibus, 400 init_in seq64::midibus, 398 init_in_sub seq64::midibus, 399 init_jack seq64::perform, 510 init_out seq64::midibus, 398 init_out_sub seq64::midibus, 398 initialize seq64::midi_splitter, 386 inner_start seq64::perform, 514 inner_stop seq64::perform, 514	seq64::sequence, 718 intersect_notes seq64::sequence, 717 intersect_triggers seq64::sequence, 717 invalid_key seq64, 79 inverse_active seq64::midi_control, 376 inverse_colors seq64::user_settings, 797, 801 is seq64::keystroke, 309 is_active seq64::perform, 483 is_adding seq64::AbstractPerfInput, 103 is_adding_pressed seq64::AbstractPerfInput, 104
init_clock seq64::mastermidibus, 360 seq64::midibus, 400 init_in seq64::midibus, 398 init_in_sub seq64::midibus, 399 init_jack seq64::perform, 510 init_out seq64::midibus, 398 init_out_sub seq64::midibus, 398 initialize seq64::midi_splitter, 386 inner_start seq64::perform, 514 inner_stop seq64::perform, 514 input_callback	seq64::sequence, 718 intersect_notes seq64::sequence, 717 intersect_triggers seq64::sequence, 717 invalid_key seq64, 79 inverse_active seq64::midi_control, 376 inverse_colors seq64::user_settings, 797, 801 is seq64::keystroke, 309 is_active seq64::perform, 483 is_adding seq64::AbstractPerfInput, 103 is_adding_pressed seq64::AbstractPerfInput, 104 is_black_key
init_clock seq64::mastermidibus, 360 seq64::midibus, 400 init_in seq64::midibus, 398 init_in_sub seq64::midibus, 399 init_jack seq64::perform, 510 init_out seq64::midibus, 398 init_out_sub seq64::midibus, 398 initialize seq64::midi_splitter, 386 inner_start seq64::perform, 514 inner_stop seq64::perform, 514 input_callback seq64::options, 427	seq64::sequence, 718 intersect_notes seq64::sequence, 717 intersect_triggers seq64::sequence, 717 invalid_key seq64, 79 inverse_active seq64::midi_control, 376 inverse_colors seq64::user_settings, 797, 801 is seq64::keystroke, 309 is_active seq64::perform, 483 is_adding seq64::AbstractPerfInput, 103 is_adding_pressed seq64::AbstractPerfInput, 104 is_black_key seq64::seqkeys, 641
init_clock seq64::mastermidibus, 360 seq64::midibus, 400 init_in seq64::midibus, 398 init_in_sub seq64::midibus, 399 init_jack seq64::perform, 510 init_out seq64::midibus, 398 init_out_sub seq64::midibus, 398 initalize seq64::midi_splitter, 386 inner_start seq64::perform, 514 inner_stop seq64::perform, 514 input_callback seq64::options, 427 input_func	seq64::sequence, 718 intersect_notes seq64::sequence, 717 intersect_triggers seq64::sequence, 717 invalid_key seq64, 79 inverse_active seq64::midi_control, 376 inverse_colors seq64::user_settings, 797, 801 is seq64::keystroke, 309 is_active seq64::perform, 483 is_adding seq64::AbstractPerfInput, 103 is_adding_pressed seq64::AbstractPerfInput, 104 is_black_key seq64::seqkeys, 641 is_channel_msg
init_clock seq64::mastermidibus, 360 seq64::midibus, 400 init_in seq64::midibus, 398 init_in_sub seq64::midibus, 399 init_jack seq64::perform, 510 init_out seq64::midibus, 398 init_out_sub seq64::midibus, 398 initalize seq64::midi_splitter, 386 inner_start seq64::perform, 514 inner_stop seq64::perform, 514 input_callback seq64::options, 427 input_func seq64::perform, 487	seq64::sequence, 718 intersect_notes seq64::sequence, 717 intersect_triggers seq64::sequence, 717 invalid_key seq64, 79 inverse_active seq64::midi_control, 376 inverse_colors seq64::user_settings, 797, 801 is seq64::keystroke, 309 is_active seq64::perform, 483 is_adding seq64::AbstractPerfInput, 103 is_adding_pressed seq64::AbstractPerfInput, 104 is_black_key seq64::seqkeys, 641 is_channel_msg seq64::event, 143
init_clock seq64::mastermidibus, 360 seq64::midibus, 400 init_in seq64::midibus, 398 init_in_sub seq64::midibus, 399 init_jack seq64::perform, 510 init_out seq64::midibus, 398 init_out_sub seq64::midibus, 398 initalize seq64::midi_splitter, 386 inner_start seq64::perform, 514 inner_stop seq64::perform, 514 input_callback seq64::options, 427 input_func	seq64::sequence, 718 intersect_notes seq64::sequence, 717 intersect_triggers seq64::sequence, 717 invalid_key seq64, 79 inverse_active seq64::midi_control, 376 inverse_colors seq64::user_settings, 797, 801 is seq64::keystroke, 309 is_active seq64::perform, 483 is_adding seq64::AbstractPerfInput, 103 is_adding_pressed seq64::AbstractPerfInput, 104 is_black_key seq64::seqkeys, 641 is_channel_msg

is_current_seq_active	seq64::event, 144
seq64::seqmenu, 650	is note off
is_current_seq_in_edit	seq64::event, 151
	is_note_off_recorded
seq64::seqmenu, 650	seq64::event, 152
is_delete	
seq64::keystroke, 309	is_note_on seq64::event, 151
is_desired_cc_or_not_cc	•
seq64::event, 144	is_null_midipulse
is_dirty_edit	seq64, 80
seq64::perform, 499	is_one_byte_msg
seq64::sequence, 711	seq64::event, 143
is_dirty_main	is_painted
seq64::perform, 498	seq64::event, 150
seq64::sequence, 711	is_pattern_playing
is_dirty_names	seq64::perform, 475, 512
seq64::perform, 499	is_press
seq64::sequence, 712	seq64::click, 108
is_dirty_perf	seq64::keystroke, 308
seq64::perform, 499	is_realized
seq64::sequence, 711	seq64::gui_window_gtk2, 246
is_dumping	is_right
seq64::mastermidibus, 361	seq64::click, 108
is_edit_sequence	is_running
seq64::perform, 473	seq64::jack_assistant, 252
seq64::seqmenu, 650	seq64::perform, 475
is_exportable	is_save
seq64::perform, 500	seq64::mainwnd, 348
is_group_learning	is_screenset_valid
seq64::perform, 506	seq64::perform, 511
is_inverse	is_selected
seq64::gui_palette_gtk2, 238	seq64::event, 150
is_jack_master	is_seq_valid
seq64::perform, 476	seq64::perform, 512
is_jack_running	is_sequence_in_edit
seq64::perform, 476	seq64::perform, 481
is_left	is_smf_0
seg64::click, 108	seq64::perform, 494
is letter	seq64::sequence, 712
seq64::keystroke, 309	is_strict_note_msg
is linked	seq64::event, 144
seq64::event, 149	is_sysex_special_id
is marked	seq64::midifile, 420
seq64::event, 150	is_two_byte_msg
is master	seq64::event, 143
seq64::jack assistant, 252	is_valid
is_middle	seq64::user_instrument, 774
seq64::click, 108	seq64::user_midi_bus, 779
is_modified	iterator
	seq64::editable_events, 130
seq64::event_list, 160	seq64::event_list, 158
seq64::perform, 472, 511	teatr eachtains
seq64::seqmenu, 649, 650	jack_assistant
is_more_input	seq64::jack_assistant, 252
seq64::mastermidibus, 360	seq64::perform, 516
is_mseq_valid	jack_frame_rate
seq64::perform, 513	seq64::jack_assistant, 258
is_note	jack_idle_connect
seq64::event, 151	seq64::gui_assistant, 213
is_note_msg	seq64::gui_assistant_gtk2, 215

jack_process_callback	seq64::keys_perform_gtk2, 302
seq64, 78	seq64::perform, 489
seq64::jack_assistant, 263	key_press_event
seq64::perform, 518	seq64::perftime, 556
jack_session_callback	keybindentry
seq64, 78	seq64::keybindentry, 272
seq64::jack_assistant, 265	seq64::perform, 516
jack_session_uuid	keys
seq64::rc_settings, 565, 569	seq64::gui_assistant, 213
jack_shutdown	seq64::perform, 475
seq64::perform, 518	keys_perform
jack_shutdown_callback	seq64::keys_perform, 281
seq64, 77	keys_perform_gtk2
seq64::jack_assistant, 263	seq64::keys_perform_gtk2, 302
jack_sync_callback	keystroke
seq64, 76	seq64::keystroke, 308
seq64::jack_assistant, 264	keyval_name
seq64::perform, 517	seg64, 79
jack_timebase_callback	keyval_normalize
seq64, 77	seq64, 79
seq64::jack_assistant, 264	kpt_bpm_dn
seq64::perform, 518	
jf_bit	seq64::keys_perform_transfer, 303
seq64::jack_status_pair_t, 271	kpt_bpm_up
jf_meaning	seq64::keys_perform_transfer, 303
seq64::jack_status_pair_t, 271	kpt_event_edit
js_clock_tick	seq64::keys_perform_transfer, 305
seq64::jack_scratchpad, 269	kpt_fast_forward
js_current_tick	seq64::keys_perform_transfer, 306
seq64::jack_scratchpad, 269	kpt_follow_transport
js_delta_tick_frac	seq64::keys_perform_transfer, 306
seq64::jack_scratchpad, 270	kpt_group_learn
js_dumping	seq64::keys_perform_transfer, 304
seq64::jack_scratchpad, 270	kpt_group_off
is init clock	seq64::keys_perform_transfer, 304
seq64::jack_scratchpad, 270	kpt_group_on
js_jack_stopped	seq64::keys_perform_transfer, 304
seq64::jack_scratchpad, 269	kpt_keep_queue
js_looping	seq64::keys_perform_transfer, 304
seq64::jack_scratchpad, 270	kpt_menu_mode
js_playback_mode	seq64::keys_perform_transfer, 306
	kpt_pattern_edit
seq64::jack_scratchpad, 270	seq64::keys_perform_transfer, 305
js_ticks_converted	kpt_pause
seq64::jack_scratchpad, 270	seq64::keys_perform_transfer, 305
js_ticks_converted_last	kpt_pointer_position
seq64::jack_scratchpad, 270	seq64::keys_perform_transfer, 306
js_ticks_delta	kpt queue
seq64::jack_scratchpad, 270	seq64::keys_perform_transfer, 304
js_total_tick	kpt replace
seq64::jack_scratchpad, 269	seq64::keys_perform_transfer, 304
keep_queue	kpt_rewind
seq64::keys_perform, 283	seq64::keys_perform_transfer, 306
Key	kpt_screenset_dn
seq64::editable_events, 130	seq64::keys_perform_transfer, 304
key	kpt_screenset_up
seq64::keystroke, 309	seq64::keys_perform_transfer, 304
	kpt_set_playing_screenset
key_name seq64::keys_perform, 292	seq64::keys_perform_transfer, 304
36404kgys_penolin, 232	5equ+key5_periorii_transier, 504

kpt_show_ui_sequence_key	seq64::eventslots, 184
seq64::keys_perform_transfer, 305	line_increment
kpt_show_ui_sequence_number	seq64::eventslots, 184
seq64::keys_perform_transfer, 305	line_maximum
kpt_snapshot_1	seq64::eventslots, 184
seq64::keys_perform_transfer, 304	link
kpt_snapshot_2	seq64::event, 149
seq64::keys_perform_transfer, 305	link_new
kpt_song_mode	seq64::event_list, 162
seq64::keys_perform_transfer, 305	seq64::sequence, 737
kpt_start	List
seq64::keys_perform_transfer, 305	seq64::triggers, 758
kpt_stop	load_events
seq64::keys_perform_transfer, 305	seq64::editable_events, 132
kpt_tap_bpm	seq64::eventslots, 185
seq64::keys_perform_transfer, 305	load_inverse_palette
kpt_toggle_jack	seq64::gui_palette_gtk2, 238
seq64::keys_perform_transfer, 306	lock
kpt_toggle_mutes	seq64::mutex, 424
seq64::keys_perform_transfer, 306	log2_time_sig_value
lash	seq64, 65
	log_main_sequence
seq64::lash, 312 lash driver	seq64::midi_splitter, 386
_	long_options
seq64, 80 lash_support	seq64, 95
seq64::rc_settings, 564, 566	lookup_keyevent_key
	seq64::keys_perform, 291
lash_support_callback	seq64::perform, 490
seq64::options, 428	lookup_keyevent_seq
lash_timeout_connect	seq64::keys_perform, 291
seq64::gui_assistant, 213	seq64::perform, 490
seq64::gui_assistant_gtk2, 215	lookup_keygroup_group
last_used_dir	seq64::keys_perform, 291
seq64::rc_settings, 566, 569	seq64::perform, 491
launch	lookup_keygroup_key
seq64::perform, 479	seq64::keys_perform, 291
launch_input_thread	seq64::perform, 491
seq64::perform, 510	m 20mda nar quartar
launch_output_thread	m_32nds_per_quarter
seq64::perform, 510	seq64::perform, 524
learn_toggle	seq64::sequence, 750
seq64::mainwnd, 344	m_4bar_offset
seq64::perform, 493	seq64::perfroll, 546
left_right_size	seq64::perftime, 557
seq64::perform, 483	m_FF_RW_button_type
legacy_format	seq64::perform, 520
seq64::rc_settings, 563, 566	m_active
length	seq64::midi_control, 377
seq64::trigger, 754	m_adding
Ifownd	seq64::AbstractPerfInput, 104
seq64::Ifownd, 315	seq64::Seq24SeqEventInput, 582
seq64::seqdata, 591	seq64::seqroll, 681
light_grey	m_adding_pressed
seq64::gui_palette_gtk2, 239	seq64::AbstractPerfInput, 104
line_after	m_adjust_bpm
seq64::configfile, 114	seq64::mainwnd, 352
line_color	m_adjust_load_offset
seq64::gui_palette_gtk2, 238	seq64::mainwnd, 352
line_count	m_adjust_ss

seq64::mainwnd, 352	m blue
m_allow_mod4_mode	seq64::gui_palette_gtk2, 242
seq64::rc_settings, 572	m_bottbox
m_allow_snap_split	seq64::eventedit, 177
seq64::rc_settings, 572	m_bottom_iterator
m_allow_two_perfedits	seq64::eventslots, 197
seq64::user_settings, 805	•
	m_box_height
m_alsa_seq	seq64::maintime, 321
seq64::mastermidibus, 364	m_box_less_pill
m_armed_saved	seq64::maintime, 322
seq64::perform, 520	m_box_width
m_armed_statuses	seq64::maintime, 321
seq64::perform, 520	m_bpm
m_auto_option_save	seq64::perfedit, 450
seq64::rc_settings, 572	m_bus
m_b_on_c_pixmap	seq64::sequence, 747
seq64::font, 201	m_bus_announce
m_b_on_y_pixmap	seq64::mastermidibus, 365
seq64::font, 201	m_buses_in
m_background	seq64::mastermidibus, 364
seq64::gui_drawingarea_gtk2, 232	m_buses_in_active
m_background_sequence	seq64::mastermidibus, 365
seq64::seqroll, 683	m_buses_in_init
seq64::sequence, 751	seq64::mastermidibus, 365
m_background_x	m_buses_out
seq64::perfroll, 545	seq64::mastermidibus, 364
m bar width	m_buses_out_active
seq64::maintime, 321	seq64::mastermidibus, 365
m_beat_length	m_buses_out_init
seq64::perfroll, 546	seq64::mastermidibus, 365
m_beat_width	m button
seq64::jack_assistant, 268	seq64::click, 110
seq64::maintime, 321	m_button_bpm
seq64::midi_timing, 391	seq64::perfedit, 449
seq64::perform, 524	seq64::seqedit, 620
m_beats	m_button_bus
seq64::midi_measures, 384	
·	seq64::seqedit, 618
m_beats_per_bar	m_button_bw
seq64::perform, 524	seq64::perfedit, 449
m_beats_per_measure	seq64::seqedit, 620
seq64::jack_assistant, 268	m_button_cancel
seq64::midi_timing, 391	seq64::eventedit, 177
m_beats_per_minute	m_button_channel
seq64::jack_assistant, 268	seq64::seqedit, 618
seq64::mastermidibus, 365	m_button_chord
seq64::midi_timing, 391	seq64::seqedit, 619
m_bg_color	m_button_collapse
seq64::gui_palette_gtk2, 243	seq64::perfedit, 448
m_bgsequence	m_button_copy
seq64::seqedit, 613	seq64::perfedit, 448
m_black	m_button_data
seq64::gui_palette_gtk2, 241	seq64::seqedit, 620
m_black_pixmap	m_button_del
seq64::font, 201	seq64::eventedit, 177
m_blk_key	m_button_down
seq64::gui_palette_gtk2, 243	seq64::mainwid, 333
m_blk_paint	m_button_expand
seq64::gui_palette_gtk2, 243	seq64::perfedit, 448
36404gui_paicilo_ginz, 243	sequapeneuit, 440

m_button_follow	m_button_tools
seq64::perfedit, 449	seq64::seqedit, 618
m_button_grow	m_button_undo
seq64::perfedit, 448	seq64::perfedit, 449
m_button_ins	seq64::seqedit, 617
seq64::eventedit, 177	m_button_xpose
m_button_jack	seq64::perfedit, 447
seq64::perfedit, 449	m button zoom
m_button_jack_connect	seq64::seqedit, 619
seq64::options, 429	m_bw
m button jack disconnect	seq64::perfedit, 450
seq64::options, 430	m_c_on_b_pixmap
m_button_jack_master	seq64::font, 201
seq64::options, 429	m_call_seq_edit
·	
m_button_jack_master_cond	seq64::mainwnd, 353
seq64::options, 429	m_call_seq_eventedit
m_button_jack_transport	seq64::mainwnd, 353
seq64::options, 429	m_category
m_button_key	seq64::editable_event, 127
seq64::seqedit, 619	m_cc
m_button_learn	seq64::seqdata, 592
seq64::mainwnd, 351	seq64::seqevent, 635
m_button_length	seq64::seqroll, 684
seq64::seqedit, 619	m_cell_h
m_button_lfo	seq64::font, 200
seq64::seqedit, 615	m_cell_w
m_button_loop	seq64::font, 200
seq64::perfedit, 448	m_channel
m_button_modify	seq64::event, 153
seq64::eventedit, 177	m_channel_count
m_button_note_length	seq64::user_midi_bus, 780
seq64::seqedit, 618	m_channel_match
m button ok	seq64::sequence, 747
seq64::options, 429	m char list
m_button_perfedit	seq64::midi_list, 381
seq64::mainwnd, 352	seq64::midifile, 421
m_button_play	m_char_vector
seq64::mainwnd, 351	seq64::midi_vector, 395
seq64::perfedit, 448	m_char_w
m_button_quantize	seq64::eventslots, 195
seq64::seqedit, 617	seq64::perfnames, 457
m_button_rec_vol	m_chord
seq64::seqedit, 620	seq64::seqedit, 613
m_button_redo	seq64::seqroll, 681
seq64::perfedit, 449	m_client
seq64::seqedit, 617	seq64::lash, 313
m_button_save	m_clip_mask
seq64::eventedit, 177	seq64::font, 202
m_button_scale	m_clipboard
seq64::seqedit, 619	seq64::seqmenu, 654
m_button_sequence	
III DUITOH SEQUENCE	•
_ ·	seq64::triggers, 771
seq64::seqedit, 618	seq64::triggers, 771 m_clock_mod
seq64::seqedit, 618 m_button_snap	seq64::triggers, 771 m_clock_mod seq64::midibus, 402
seq64::seqedit, 618 m_button_snap seq64::perfedit, 448	seq64::triggers, 771 m_clock_mod seq64::midibus, 402 m_clock_type
seq64::seqedit, 618 m_button_snap seq64::perfedit, 448 seq64::seqedit, 618	seq64::triggers, 771 m_clock_mod seq64::midibus, 402 m_clock_type seq64::midibus, 402
seq64::seqedit, 618 m_button_snap seq64::perfedit, 448 seq64::seqedit, 618 m_button_stop	seq64::triggers, 771 m_clock_mod seq64::midibus, 402 m_clock_type seq64::midibus, 402 m_clocks_per_metronome
seq64::seqedit, 618 m_button_snap seq64::perfedit, 448 seq64::seqedit, 618	seq64::triggers, 771 m_clock_mod seq64::midibus, 402 m_clock_type seq64::midibus, 402

m_cond	m_divs_per_beat
seq64::condition_var, 112	seq64::perfroll, 545
m_condition_var	m_dk_blue
seq64::perform, 527	seq64::gui_palette_gtk2, 241
m_config_directory	m_dk_cyan
seq64::rc_settings, 574	seq64::gui_palette_gtk2, 242
m_config_filename	m_dk_green
seq64::rc_settings, 574	seq64::gui_palette_gtk2, 241
m_config_filename_alt	m_dk_grey
seq64::rc_settings, 575	seq64::gui_palette_gtk2, 242
m_control_height	m_dk_magenta
seq64::user_settings, 804	seq64::gui_palette_gtk2, 242
m_control_status	m_dk_orange
seq64::perform, 526	seq64::gui_palette_gtk2, 241
m_controller_count	m_dk_red
seq64::user_instrument, 776	seq64::gui_palette_gtk2, 241
m_current_event	m_dont_reset_ticks
seq64::editable_events, 135	seq64::perform, 526
m_current_index	m_drag_handle
seq64::eventslots, 196	seq64::seqdata, 593
m current iterator	m_drag_paste_start_pos
seq64::eventslots, 197	seq64::FruitySeqRollInput, 211
m_current_seq	m_dragging
seq64::seqmenu, 654	seq64::seqdata, 593
	·
m_current_x	m_drawing_background_seq
seq64::FruityPerfInput, 206	seq64::seqroll, 684
seq64::gui_drawingarea_gtk2, 233	m_drop_sequence
m_current_y	seq64::perfroll, 547
seq64::FruityPerfInput, 206	m_drop_tick
seq64::gui_drawingarea_gtk2, 233	seq64::perfroll, 547
m_current_zoom	m_drop_tick_trigger_offset
seq64::user_settings, 804	seq64::perfroll, 547
m_d	m_drop_x
seq64::configfile, 115	seq64::gui_drawingarea_gtk2, 233
m_data	m_drop_y
seq64::event, 153	seq64::gui_drawingarea_gtk2, 233
seq64::midi_control, 378	m_dumping_input
seq64::midifile, 421	seq64::mastermidibus, 366
m_dest_addr_client	m_edit_sequence
seq64::midibus, 402	seq64::perform, 527
m_dest_addr_port	m_editbox
seq64::midibus, 403	seq64::eventedit, 177
m_device_ignore	m_editing
seq64::rc_settings, 574	seq64::sequence, 749
m_device_ignore_num	m_editing_cc
seq64::rc_settings, 574	seq64::seqedit, 621
m_dirty_edit	m_editing_status
seq64::sequence, 748	seq64::seqedit, 621
m_dirty_main	m_effective_tick
seq64::sequence, 748	seq64::Seq24PerfInput, 580
m_dirty_names	m_entry_bpm
seq64::sequence, 749	seq64::perfedit, 449
m_dirty_perf	seq64::seqedit, 620
seq64::sequence, 749	m_entry_bus
m_disable_reported	seq64::seqedit, 618
seq64::midifile, 421	m_entry_bw
m_divisions	seq64::perfedit, 449
	seq64::seqedit, 620
seq64::midi_measures, 384	354043545uit, 020

m_entry_channel	seq64::sequence, 746
seq64::seqedit, 618	m_eventslots
m_entry_chord	seq64::eventedit, 176
seq64::seqedit, 620	m_excell_FF_RW
m_entry_data	seq64::perform, 520
seq64::seqedit, 620	m_fg_color
m_entry_ev_data_0	seq64::gui_palette_gtk2, 243
seq64::eventedit, 179	m_file_size
m_entry_ev_data_1	seq64::midifile, 420
seq64::eventedit, 179	m_filename
m_entry_ev_name	seq64::rc_settings, 574
seq64::eventedit, 179	m_filter_by_channel
m_entry_ev_timestamp	seq64::mastermidibus, 366
seq64::eventedit, 178	seq64::rc_settings, 573
m_entry_key	m_flash_height
seq64::seqedit, 619	seq64::maintime, 322
m_entry_length	m flash width
seq64::seqedit, 619	seq64::maintime, 322
m_entry_name	m flash x
seq64::seqedit, 621	seq64::maintime, 322
m_entry_note_length	m_follow_transport
	·
seq64::seqedit, 619	seq64::jack_assistant, 268
m_entry_notes	m_font_h
seq64::mainwnd, 352	seq64::font, 200
m_entry_scale	m_font_w
seq64::seqedit, 619	seq64::font, 200
m_entry_sequence	m_foreground
seq64::seqedit, 618	seq64::gui_drawingarea_gtk2, 232
m_entry_snap	m_format_timestamp
seq64::perfedit, 448	seq64::editable_event, 127
seq64::seqedit, 618	m_fruity_interaction
m_entry_xpose	seq64::perfroll, 547
seq64::perfedit, 447	seq64::seqevent, 633
m entry zoom	seq64::seqroll, 680
seq64::seqedit, 619	m_gc
m_erase_painting	seq64::gui drawingarea gtk2, 232
seq64::FruitySeqRollInput, 211	m_global_bgsequence
m_error_is_fatal	seq64::midifile, 422
seq64::midifile, 421	m global seq feature save
m error message	seq64::user settings, 804
seq64::midifile, 421	m gmute tracks
m_event_container	seq64::user settings, 808
seq64::eventslots, 195	m green
m_event_count	_6
	seq64::gui_palette_gtk2, 242
seq64::eventslots, 196	m_grey
m_eventedit	seq64::gui_palette_gtk2, 242
seq64::seqmenu, 654	m_grid_brackets
m_events	seq64::user_settings, 803
seq64::editable_events, 135	m_grid_style
seq64::event_list, 165	seq64::user_settings, 803
seq64::sequence, 746	m_grow_direction
m_events_clipboard	seq64::perfroll, 548
seq64::sequence, 746	m_growing
m_events_redo	seq64::perfroll, 548
seq64::sequence, 747	seq64::seqevent, 634
m_events_undo	seq64::seqroll, 682
seq64::sequence, 746	m_gui_support
m_events_undo_hold	seq64::perform, 520

m_initial_note_length
seq64::seqedit, 612
m_initial_snap
seq64::seqedit, 612
m_initial_zoom
seq64::seqedit, 612
m_inputing
seq64::midibus, 402
seq64::perform, 523
m_instrument_def
seq64::user_instrument, 776
m_instruments
seq64::user_settings, 803
m_interaction
seq64::perfroll, 548
m_interaction_method
seq64::rc_settings, 574
m_inverse_active
seq64::midi control, 377
m_inverse_colors
seq64::user_settings, 806
m_is_drag_pasting
seq64::FruitySeqEventInput, 209
seq64::seqroll, 682
m_is_drag_pasting_start
seq64::FruitySeqEventInput, 209
seq64::seqroll, 682
m_is_inverse
seq64::gui_palette_gtk2, 241
m_is_lash_supported
seq64::lash, 313
m_is_modified
seq64::event_list, 165
seq64::perform, 527
m_is_pattern_playing
seq64::perform, 523
m_is_press
seq64::click, 109
seq64::keystroke, 310
m_is_realized
seq64::gui_window_gtk2, 248
m_is_running
seq64::mainwnd, 353
seq64::perfedit, 450
m_is_valid
seq64::user_instrument, 776
seq64::user_midi_bus, 780
m_iterator_draw
seq64::sequence, 747
m_iterator_draw_trigger
seq64::triggers, 771
m_iterator_play_trigger
seq64::triggers, 771
m_jack_asst
seq64::perform, 528
m_jack_client
seq64::jack_assistant, 266
m_jack_client_name

seq64::jack_assistant, 266	seq64::keys_perform, 299
m_jack_client_uuid	m_key_groups
seq64::jack_assistant, 266	seq64::keys_perform, 297
m_jack_frame_current	m_key_groups_rev
seq64::jack_assistant, 266	seq64::keys_perform, 298
m_jack_frame_last	m_key_keep_queue
seq64::jack_assistant, 267	seq64::keys_perform, 298
m_jack_frame_rate	m_key_menu_mode
seq64::jack_assistant, 267	seq64::keys_perform, 299
m_jack_master	m_key_pattern_edit
seq64::jack_assistant, 267	seq64::keys_perform, 300
m_jack_parent	m_key_pause
seq64::jack_assistant, 266	seq64::keys_perform, 299
m_jack_pos	m_key_pointer_position
seq64::jack_assistant, 267	seq64::keys_perform, 300
m_jack_running	m_key_queue
seq64::jack_assistant, 267	seq64::keys_perform, 298
m_jack_session_uuid	m_key_replace
seq64::rc_settings, 574	seq64::keys_perform, 298
m_jack_stop_tick	m_key_rewind
seq64::jack_assistant, 268	seq64::keys_perform, 300
m_jack_tick	m_key_screenset_dn
seq64::jack_assistant, 267	seq64::keys_perform, 299
seq64::perform, 525	m_key_screenset_up
m_jack_transport_state	seq64::keys_perform, 298
seq64::jack_assistant, 267	m_key_set_playing_screenset
m_jack_transport_state_last	seq64::keys_perform, 299
seq64::jack_assistant, 267	m_key_show_ui_sequence_key
m_jsession_ev	seq64::keys_perform, 297
seq64::jack_assistant, 267	m_key_show_ui_sequence_number
m_justselected_one	seq64::keys_perform, 297
seq64::FruitySeqEventInput, 209	m_key_snapshot_1
seq64::seqroll, 682	seq64::keys_perform, 298
m_key	m_key_snapshot_2
seq64::keybindentry, 273	seq64::keys_perform, 298
seq64::keystroke, 310	m_key_song_mode
seq64::seqedit, 613	seq64::keys_perform, 299
seq64::seqkeys, 645	m_key_start
seq64::seqroll, 681	seq64::keys_perform, 299
m_key_bpm_dn	m_key_stop
seq64::keys_perform, 298	seq64::keys_perform, 300
m_key_bpm_up	m_key_tap_bpm
seq64::keys_perform, 298	seq64::keys_perform, 300
m_key_event_edit	m_key_toggle_jack
seq64::keys_perform, 300	seq64::keys_perform, 299
m_key_events	m_key_toggle_mutes
seq64::keys_perform, 297	seq64::keys_perform, 300
m_key_events_rev	m_keying
seq64::keys_perform, 297	seq64::seqkeys, 645
m_key_fast_forward	m_keying_note
seq64::keys_perform, 300	seq64::seqkeys, 645
m_key_follow_transport	m_keys_perform
seq64::keys_perform, 300	seq64::gui_assistant, 214
m_key_group_learn	m_label_category
seq64::keys_perform, 299	seq64::eventedit, 178
m_key_group_off	m_label_channel
seq64::keys_perform, 299	seq64::eventedit, 178
m_key_group_on	m_label_ev_count
·	_

ang64::avantadit 179	m It grov
seq64::eventedit, 178	m_lt_grey
m_label_modified	seq64::gui_palette_gtk2, 243
seq64::eventedit, 178	m_main_cursor
m_label_ppqn	seq64::mainwnd, 351
seq64::eventedit, 178	m_main_time
m_label_right	seq64::mainwnd, 351
seq64::eventedit, 179	m_main_wid
m_label_seq_name	seq64::mainwnd, 350
seq64::eventedit, 178	m_mainperf
m_label_spacer	seq64::gui_drawingarea_gtk2, 232
seq64::eventedit, 178	seq64::gui_window_gtk2, 247
m_label_time_fmt	seq64::options, 429
seq64::eventedit, 179	seq64::seqmenu, 654
m_label_time_sig	m_mainwid_border
seq64::eventedit, 178	seq64::mainwid, 335
m_lash_args	seq64::user_settings, 804
seq64::lash, 313	m_mainwid_spacing
m_lash_support	seq64::mainwid, 335
seq64::rc_settings, 572	seq64::user_settings, 804
m_last_playing	m_mainwid_x
seq64::mainwid, 334	seq64::mainwid, 335
m_last_tick	seq64::user_settings, 809
seq64::sequence, 749	m_mainwid_y
m_last_tick_x	seq64::mainwid, 335
seq64::mainwid, 334	seq64::user_settings, 809
m_last_used_dir	m_mainwnd_cols
seq64::rc_settings, 574	seq64::mainwid, 334
m_lasttick	seq64::user_settings, 804
seq64::midibus, 403	m_mainwnd_rows
m_left_marker_tick	seq64::mainwid, 334
seq64::perftime, 557	seq64::user_settings, 803
m_left_tick	m_manual_alsa_ports
seq64::perform, 525	seq64::rc_settings, 573
m_legacy_format	m marked
seq64::rc_settings, 572	seq64::event, 153
m_length	m_master_bus
seq64::sequence, 750	seq64::perform, 522
seq64::triggers, 772	m_masterbus
m_lfo_wnd	seq64::sequence, 747
seq64::seqedit, 616	m_max_busses
m_line	seq64::mastermidibus, 364
seq64::configfile, 115	m max sequence
· · · · · · · · · · · · · · · · · · ·	seq64::user_settings, 809
m_line_color	
seq64::gui_palette_gtk2, 243	m_max_sets
m_line_count	seq64::mainwid, 335
seq64::eventslots, 196	seq64::perform, 527
m_line_maximum	seq64::user_settings, 804
seq64::eventslots, 196	m_max_value
m_line_overlap	seq64::midi_control, 378
seq64::eventslots, 196	m_maxbeats
m_linked	seq64::sequence, 749
seq64::event, 153	m_measure_length
m_local_addr_client	seq64::perfroll, 546
seq64::midibus, 403	seq64::perftime, 557
m_local_addr_port	m_measures
seq64::midibus, 403	seq64::midi_measures, 384
m_looping	seq64::seqedit, 613
seq64::perform, 523	m_menu

0.500	
seq64::seqmenu, 654	seq64::user_settings, 803
m_menu_bpm	m_midi_buss_override
seq64::perfedit, 450	seq64::user_settings, 808
seq64::seqedit, 615	m_midi_cc_off
m_menu_bw	seq64::perform, 526
seq64::perfedit, 450	m_midi_cc_on
seq64::seqedit, 615	seq64::perform, 526
m_menu_chords	m_midi_cc_toggle
seq64::seqedit, 615	seq64::perform, 526
m_menu_data	m_midi_channel
seq64::seqedit, 615	seq64::sequence, 747
m_menu_edit	m_midi_parameters
seq64::mainwnd, 350	seq64::editable_events, 135
m_menu_file	m_midi_ppqn
seq64::mainwnd, 350	seq64::user_settings, 807
m_menu_help	m_midiclockpos
seq64::mainwnd, 350	seq64::perform, 526
m_menu_key	m midiclockrunning
seq64::seqedit, 615	seq64::perform, 525
m menu length	m midiclocktick
seq64::seqedit, 614	seq64::perform, 525
m_menu_midibus	m_min_value
seq64::seqedit, 615	seq64::midi_control, 378
m_menu_midich	m_mode_group
seq64::seqedit, 615	seq64::perform, 520
·	• •
m_menu_mode	m_mode_group_learn
seq64::mainwnd, 353	seq64::perform, 521
m_menu_note_length	m_modified
seq64::seqedit, 614	seq64::seqmenu, 654
m_menu_rec_vol	m_modifier
seq64::seqedit, 616	seq64::click, 110
m_menu_scale	seq64::keystroke, 310
seq64::seqedit, 615	m_move_delta_x
m_menu_sequences	seq64::seqroll, 682
seq64::seqedit, 615	m_move_delta_y
m_menu_snap	seq64::seqroll, 683
seq64::perfedit, 447	m_move_snap_offset_x
seq64::seqedit, 614	seq64::seqevent, 635
m_menu_tools	seq64::seqroll, 683
seq64::seqedit, 614	m_moving
m_menu_view	seq64::mainwid, 334
seq64::mainwnd, 350	seq64::perfroll, 548
m_menu_xpose	seq64::seqevent, 634
seq64::perfedit, 447	seq64::seqroll, 682
m_menu_zoom	m_moving_init
seq64::seqedit, 614	seq64::seqevent, 634
m menubar	seq64::seqroll, 682
seq64::mainwnd, 350	m_moving_seq
seq64::seqedit, 614	seq64::mainwid, 333
m_midi_beat_width	m_musical_key
seq64::user_settings, 808	seq64::sequence, 751
m_midi_beats_per_measure	m_musical_scale
seq64::user_settings, 807	seq64::sequence, 751
m_midi_beats_per_minute	m_mute_group
seq64::user_settings, 808	seq64::perform, 520
m_midi_bus_def	m_mute_group_selected
seq64::user_midi_bus, 780 m_midi_buses	seq64::perform, 521 m_mutex

seq64::mastermidibus, 366	seq64::seqdata, 592
seq64::midibus, 403	m_number_offset_y
seq64::midifile, 420	seq64::seqdata, 592
seq64::sequence, 752	m_number_w
m_mutex_lock	seq64::seqdata, 592
seq64::mutex, 424	m_numbers
m_name	seq64::seqdata, 593
seq64::configfile, 115	m_offset
seq64::midibus, 403	seq64::font, 200
seq64::midifile, 421	seq64::perform, 526
seq64::sequence, 749	seq64::trigger, 755
m_name_category	m_old
seq64::editable_event, 127	seq64::seqdata, 593
m_name_channel	seq64::seqevent, 634
seq64::editable_event, 128	seq64::seqroll, 680
m_name_data	m_old_progress_ticks
seq64::editable_event, 128	seq64::perfroll, 546
m_name_meta	m_old_seq
seq64::editable_event, 128	seq64::mainwid, 334
m_name_seqspec	m_one_measure
seq64::editable_event, 128	seq64::perform, 524
m_name_status	m_options
seq64::editable_event, 128	seq64::mainwnd, 351
m_name_timestamp	m_optsbox
seq64::editable_event, 127	seq64::eventedit, 177
m_namebox_w	m_orange
seq64::perfnames, 458	seq64::gui_palette_gtk2, 242
m_names_chars	m_out_thread
seq64::perfnames, 457	seq64::perform, 522
m_names_x	m_out_thread_launched
seq64::perfnames, 458	seq64::perform, 523
m_names_y	m_outputing
seq64::perfnames, 458	seq64::perform, 523
seq64::perfroll, 545	m_padded_h
m_new_format	seq64::font, 200
seq64::midifile, 422	m_page_factor
m_note_length	seq64::perfroll, 545
seq64::seqedit, 613	m_pager_index
seq64::seqroll, 681	seq64::eventslots, 197
m_note_off_margin	m_painted
seq64::sequence, 752	seq64::event, 154
m_note_off_velocity	m_painting
seq64::sequence, 751	seq64::seqevent, 635
m_note_on_velocity	seq64::seqroll, 682
seq64::sequence, 751	m_parent
m_notebook	seq64::editable_event, 127
seq64::options, 430	seq64::eventslots, 195
m_notes_on	seq64::perfnames, 457
seq64::sequence, 747	seq64::perfroll, 544
m_notify	seq64::perftime, 557
seq64::perform, 528	seq64::sequence, 746
m_num_in_buses	seq64::triggers, 771
seq64::mastermidibus, 364	m_pass_sysex
m_num_out_buses	seq64::rc_settings, 573
seq64::mastermidibus, 364	
5040 1nastormaisas, 00 1	m_paste
m_num_poll_descriptors	m_paste seq64::seqevent, 635
m_num_poll_descriptors seq64::mastermidibus, 366	
m_num_poll_descriptors	seq64::seqevent, 635

seq64::triggers, 772	seq64::midifile, 422
m_peer_perfedit	seq64::perfedit, 450
seq64::perfedit, 446	seq64::perform, 524
m_perf	seq64::perfroll, 545
seq64::keybindentry, 273	seq64::perftime, 557
m_perf_edit	seq64::seqedit, 613
seq64::mainwnd, 351	seq64::seqevent, 633
m_perf_edit_2	seq64::seqroll, 681
seq64::mainwnd, 351	seq64::seqtime, 689
m_perf_scale_x	seq64::sequence, 750
seq64::perfroll, 545	seq64::triggers, 772
seq64::perftime, 558	m_print_keys
m_perfnames	seq64::rc_settings, 573
seq64::perfedit, 447	m_priority
m_perform	seq64::rc_settings, 573
seq64::lash, 313	m_progress_bar_colored
m_perfroll	seq64::user_settings, 806
seq64::perfedit, 447	m_progress_bar_thick
m_perftime	seq64::user_settings, 806
seq64::perfedit, 447	m_progress_color
m_phase	seq64::gui_palette_gtk2, 243
seq64::lfownd, 317	m_progress_height
m_pill_width	seq64::mainwid, 336
seq64::maintime, 321	m_progress_x
m_pixmap	seq64::seqroll, 683
seq64::font, 201	m_quantized_rec
seq64::gui_drawingarea_gtk2, 232	seq64::sequence, 748
m_playback_mode	m queue
seq64::perform, 523	seq64::mastermidibus, 365
m_playing	seq64::midibus, 403
seq64::sequence, 748	m_queued
m_playing_notes	seq64::sequence, 748
seq64::sequence, 748	m_queued_tick
m_playing_screen	seq64::sequence, 749
seq64::perform, 521	
m_playscreen_offset	m_raise
_, · _	seq64::sequence, 749
seq64::perform, 521	m_range
m_poll_descriptors	seq64::lfownd, 317
seq64::mastermidibus, 366	m_rank
m_pos	seq64::event_list::event_key, 155
seq64::midifile, 421	m_rec_vol
seq64::seqroll, 680	seq64::sequence, 751
m_position_for_get	m_recording
seq64::midi_container, 374	seq64::sequence, 748
m_pp_eighth	m_red
seq64::seqedit, 613	seq64::gui_palette_gtk2, 242
m_pp_sixteenth	m_redo_stack
seq64::seqedit, 614	seq64::triggers, 771
m_pp_whole	m_redo_vect
seq64::seqedit, 613	seq64::perform, 528
m_ppqn	m_redraw_period_ms
seq64::jack_assistant, 268	seq64::gui_window_gtk2, 248
seq64::maintime, 322	m_reposition
seq64::mainwnd, 350	seq64::perform, 520
seq64::mastermidibus, 365	m_reveal_alsa_ports
seq64::midi_splitter, 388	seq64::rc_settings, 573
seq64::midi_timing, 391	m_right_marker_tick
seq64::midibus, 402	seq64::perftime, 558
30q0 (mmaisao, 10L	coqo importanto, coo

m_right_tick	seq64::seqroll, 681
seq64::perform, 525	m_seq
m_rightbox	seq64::eventedit, 179
seq64::eventedit, 177	seq64::eventslots, 195
m_roll_length_ticks	seq64::lfownd, 316
seq64::perfroll, 547	seq64::mastermidibus, 366
m_running	seq64::midibus, 402
seq64::perform, 523	seq64::seqdata, 592
m_safety_mutex	seq64::seqedit, 614
seq64::automutex, 106	seq64::seqevent, 633
m_save_user_config	seq64::seqkeys, 644
seq64::user_settings, 810	seq64::seqroll, 680
m_scale	seq64::seqtime, 689
seq64::seqedit, 613	m_seq24_interaction
seq64::seqkeys, 645	seq64::perfroll, 548
seq64::seqroll, 681	seq64::seqevent, 633
m_scale_phase	m_seq_number
seq64::lfownd, 316	seq64::sequence, 750
m_scale_range	m_seqarea_seq_x
seq64::lfownd, 316	seq64::mainwid, 335
m_scale_speed	seq64::user_settings, 809
seq64::Ifownd, 316	m_seqarea_seq_y
m_scale_value	seq64::mainwid, 335
seq64::lfownd, 316	seq64::user_settings, 809
m_scale_wave	m_seqarea_x
seq64::lfownd, 316	seq64::mainwid, 334
m_screen_set_notepad	seq64::user_settings, 809
seq64::perform, 526	m_seqarea_y
m_screenset	seq64::mainwid, 334
seq64::mainwid, 334	seq64::user_settings, 809
seq64::perform, 526	m_seqchars_x
m_screenset_offset	seq64::user_settings, 807
seq64::mainwid, 336	m_seqchars_y
m_screenset_slots	seq64::user_settings, 807
seq64::mainwid, 335	m_seqdata
m_scroll_offset_key	seq64::lfownd, 316
seq64::seqkeys, 644	m_seqdata_wid
seq64::seqroll, 683	seq64::seqedit, 616
m_scroll_offset_ticks	seq64::seqevent, 634
seq64::seqdata, 592	m_seqedit
seq64::seqevent, 634	seq64::seqmenu, 654
seq64::seqroll, 683	m_seqedit_bgsequence
seq64::seqtime, 689	seq64::user_settings, 805
m_scroll_offset_x	m_seqedit_key
seq64::seqdata, 592	seq64::user_settings, 805
seq64::seqevent, 634	m_seqedit_scale
seq64::seqroll, 683	seq64::user_settings, 805
seq64::seqtime, 689	m_seqevent_wid
m_scroll_offset_y	seq64::seqedit, 617
seq64::seqkeys, 644	m_seqkeys_wid
seq64::seqroll, 683	seq64::seqedit, 616
m_selected	seq64::seqroll, 680
seq64::event, 153	m_seqroll_wid
seq64::seqevent, 634	seq64::seqedit, 617
seq64::seqroll, 680	m_seqs
seq64::trigger, 756	seq64::perform, 521
m_selecting	m_seqs_active
seq64::seqevent, 634	seq64::perform, 521

m_seqs_in_set	seq64::seqedit, 613
seq64::perfnames, 458	seq64::seqevent, 633
seq64::perform, 527	seq64::seqroll, 681
seq64::user_settings, 808	m_snap_tick
m_seqtime_wid	seq64::sequence, 750
seq64::seqedit, 616	m_song_mute
m_sequence	seq64::sequence, 747
seq64::editable_events, 135	m_song_start_mode
seq64::midi_container, 374	seq64::perform, 519
m_sequence_active	m_speed
seq64::perfnames, 458	seq64::lfownd, 317
seq64::perfroll, 547	m_spinbutton_bpm
m_sequence_count	seq64::mainwnd, 352
seq64::perform, 527	m_spinbutton_load_offset
m_sequence_max	seq64::mainwnd, 352
seq64::perfnames, 458	m_spinbutton_ss
seq64::perform, 527	seq64::mainwnd, 352
seq64::perfroll, 547	m_standard_bpm
m_sequence_offset	seq64::perfedit, 450
seq64::perfnames, 458	m_start_from_perfedit
seq64::perfroll, 546	seq64::perform, 519
m_sequence_state	m_starting_tick
seq64::perform, 522	seq64::perform, 525
m_setbox_w	m_stats
seq64::eventslots, 195	seq64::rc_settings, 573
seq64::perfnames, 457	m_status
m_show_midi	seq64::event, 152
seq64::rc_settings, 572	seq64::midi_control, 377
m_show_octave_letters	seq64::seqdata, 592
seq64::seqkeys, 645	seq64::seqevent, 635
m_showbox	seq64::seqroll, 684
seq64::eventedit, 177	m_sysex
m_sigpipe	seq64::event, 153
seq64::mainwnd, 350	m_sysex_size
m_size_box_w	seq64::event, 153
seq64::perfroll, 545	m_table
m_slot	seq64::eventedit, 176
seq64::keybindentry, 273	seq64::perfedit, 446
m_slots_chars	seq64::seqedit, 617
seq64::eventslots, 195	m_text_size_x
m_slots_x	seq64::mainwid, 335
seq64::eventslots, 196	m_text_size_y
m_slots_y	seq64::mainwid, 335
seq64::eventslots, 196	m text x
m_smf0_channels	seq64::user_settings, 807
seq64::midi splitter, 388	m text y
m smf0 channels count	seq64::user_settings, 807
seq64::midi_splitter, 388	m thru
m_smf0_main_sequence	seq64::sequence, 748
seq64::midi_splitter, 388	m tick
m_smf0_seq_number	seq64::maintime, 322
seq64::midi_splitter, 388	seq64::perform, 525
m_smf0_splitter	m_tick_end
seq64::midifile, 422	seq64::trigger, 755
m_snap	m_tick_offset
seq64::perfedit, 450	seq64::perftime, 557
seq64::perfroll, 544	m tick start
seq64::perftime, 557	seq64::trigger, 755
36404pentine, 337	sequ4ingger, 755

m_ticks_per_bar	seq64::triggers, 771
seq64::perfroll, 545	m_undo_vect
m_time_beat_width	seq64::perform, 528
seq64::sequence, 750	m_us_per_quarter_note
m_time_beats_per_measure	seq64::perform, 524
seq64::sequence, 750	seq64::sequence, 751
m_timearea_y	m_use_default_ppqn
seq64::perftime, 558	seq64::midi_splitter, 388
m_timeout_connect	seq64::midifile, 422
seq64::mainwnd, 353	m_use_more_icons
m_timestamp	seq64::user_settings, 806
seq64::event, 152	m_use_new_font
seq64::event_list::event_key, 155	seq64::font, 200
m_toggle_jack	seq64::user_settings, 805
seq64::jack_assistant, 268	m usemidiclock
m_toggle_play	seq64::perform, 525
seq64::seqedit, 620	m_user_filename
m_toggle_q_rec	seq64::rc_settings, 574
seq64::seqedit, 621	m_user_filename_alt
m_toggle_record	seq64::rc_settings, 575
seq64::seqedit, 621	m_v_page_increment
m_toggle_thru	seq64::perfroll, 544
seq64::seqedit, 621	m_v_perf_page_increment
m_toggle_transpose	seq64::user_settings, 806
seq64::seqedit, 614	m_vadjust
m_tooltips	seq64::eventedit, 176
seq64::mainwnd, 350	seq64::gui_drawingarea_gtk2, 232
seq64::options, 429	seq64::perfedit, 446
seq64::perfedit, 450	seq64::seqedit, 616
seq64::seqedit, 620	m_value
m_top_index	seq64::lfownd, 316
seq64::eventslots, 196	m_vbox
m_top_iterator	seq64::seqedit, 617
seq64::eventslots, 196	m_vector_sequence
m_total_seqs	seq64::mastermidibus, 366
seq64::user_settings, 808	m_vertical_adjust
m_tracks_mute_state	seq64::seqroll, 680
seq64::perform, 520	m_vscroll
m_trans_button_press	seq64::eventedit, 176
seq64::perfroll, 546	seq64::perfedit, 447
seq64::seqroll, 683	m_vscroll_new
m_transport_follow	seq64::seqedit, 616
seq64::perfroll, 546	m_was_active_edit
seq64::seqroll, 683	seq64::perform, 522
m_transposable	m_was_active_main
seq64::sequence, 747	seq64::perform, 521
m_transpose	m_was_active_names
seq64::perform, 522	seq64::perform, 522
m_trigger_copied	m_was_active_perf
seq64::triggers, 771	seq64::perform, 522
m_trigger_offset	m_was_playing
seq64::sequence, 749	seq64::sequence, 748
m_triggers	m_wave
seq64::sequence, 746	seq64::Ifownd, 317
seq64::triggers, 771	m_white
m_type	seq64::gui_palette_gtk2, 242
seq64::keybindentry, 273	m_white_pixmap
m_undo_stack	seq64::font, 201
	• ′

m_wht_key	mainwnd_cols
seq64::gui_palette_gtk2, 243	seq64::user_settings, 793, 797
m_wht_paint	mainwnd_key_event
seq64::gui_palette_gtk2, 243	seq64::perform, 496
m_window	mainwnd_rows
seq64::gui_drawingarea_gtk2, 232	seq64::user_settings, 793, 797
m_window_redraw_rate_ms	make_clock
seq64::user_settings, 806	seq64::event, 150
m_window_x	make_directory
seq64::gui_drawingarea_gtk2, 233	seq64, 76
seq64::gui_window_gtk2, 247	make_section_name
m_window_y	seq64, 82
seq64::gui_drawingarea_gtk2, 233	manual_alsa_ports
seq64::gui_window_gtk2, 247	seq64::rc_settings, 565, 568
m_with_jack_master	mark
seq64::rc_settings, 573	seq64::event, 150
m_with_jack_master_cond	mark_all
seq64::rc_settings, 573	seq64::event_list, 163
m_with_jack_transport	mark_out_of_range
seq64::rc_settings, 573	seq64::event_list, 162
m x	mark selected
_ seq64::click, 109	seq64::event list, 162
m_xy_offset	seq64::sequence, 736
seq64::perfnames, 458	master bus
m_y	seq64::perform, 475
seq64::click, 109	mastermidibus
m_y_on_b_pixmap	seq64::mastermidibus, 356
seq64::font, 201	seq64::midibus, 402
m_yellow	match
seq64::gui_palette_gtk2, 242	seq64::midi_control, 377
m zoom	max_active_set
seq64::perfroll, 545	seq64::perform, 510
seq64::seqdata, 592	max sequence
seq64::seqedit, 612	seq64::user_settings, 793
seq64::seqevent, 633	max sets
seq64::seqroll, 681	seq64::user settings, 793, 798
seq64::seqtime, 689	max value
maintime	seq64::midi_control, 376
seq64::maintime, 320	max zoom
mainwid	seq64::user_settings, 800
seq64::mainwid, 326	mc_baseline_ppqn
mainwid_border	seq64::user settings, 810
seq64::user_settings, 794, 799	mc max zoom
mainwid_grid_style_t	seq64::user_settings, 810
seq64::user_settings, 789	mc_min_zoom
mainwid_spacing	seq64::user settings, 810
seq64::user settings, 794, 799	measures
mainwid x	seq64::midi_measures, 383
seq64::user_settings, 795	measures_to_ticks
mainwid_y	seq64, 70
seq64::user_settings, 795	seq64::sequence, 705
mainwnd	measurestring_to_pulses
seq64::maintime, 321	seq64, 61
seq64::mainwid, 333	menu_mode
seq64::mainwnd, 341	seq64::keys_perform, 288
seq64::perform, 516	merge
seq64::rc_settings, 571	seq64::event_list, 161
seq64::seqmenu, 654	meta_string
	···

seq64::editable_event, 125	seq64::click, 109
midi_beat_width	seq64::keystroke, 310
seq64::user_settings, 800, 802	mod_control_shift
midi_beats_per_bar	seq64::click, 109
seq64::user_settings, 799, 802	seq64::keystroke, 310
midi_beats_per_minute	mod_last_tick
seq64::user_settings, 800, 802	seq64::sequence, 709
midi_buss_override	mod_super
seq64::user_settings, 800, 801	seq64::click, 109
midi_container	seq64::keystroke, 310
seq64::event_list, 165	mod_timestamp
seq64::midi_container, 369	seq64::event, 145
seq64::triggers, 770	modifier
midi_control	seq64::click, 109
seq64::midi_control, 376	seq64::keystroke, 310
midi_control_off	modify
seq64::perform, 502	seq64::perform, 472
midi_control_on	seq64::sequence, 702
seq64::perform, 502	modify_current_event
midi_control_toggle	seq64::eventslots, 187
seq64::perform, 502	motion_notify
midi_list	seq64::seqroll, 673
seq64::midi_list, 380	mouse_action
midi_measures	seq64::seqedit, 609
seq64::midi_measures, 382 midi_measures_to_pulses	mouse_action_e seq64, 57
seq64, 61	mouse_fruity_callback
•	seq64::options, 428
midi_ppqn seq64::user_settings, 799, 801	mouse_mod4_callback
midi_splitter	seq64::options, 428
seq64::event_list, 165	mouse_seq24_callback
seq64::midi_splitter, 385	seq64::options, 428
midi_timing	mouse_snap_split_callback
seq64::midi_timing, 389	seq64::options, 428
midi_vector	move
seq64::midi_vector, 393	seq64::triggers, 767
midibus	move_selected
seq64::midibus, 397	seq64::triggers, 766
midibyte	move_selected_notes
seq64, 53	seq64::seqroll, 670
midifile	seq64::sequence, 728
seq64::midi_container, 374	move_selected_triggers_to
seq64::midifile, 406	seq64::sequence, 719
seq64::perform, 516	move_selection_box
seq64::triggers, 770	seq64::seqroll, 670
midilong	move_triggers
seq64, 53	seq64::perform, 497
midipulse	seq64::sequence, 720
seq64, 54	moving
midishort	seq64::seqroll, 676
seq64, 53	multiply_pattern
min	seq64::sequence, 741
seq64, 82	musical_key
min_value	seq64::sequence, 741
seq64::midi_control, 376	musical_scale
min_zoom	seq64::sequence, 742
seq64::user_settings, 800	mute_all_tracks
mod_control	seq64::perform, 486

seq64::seqmenu, 653	seq64::Seq24PerfInput, 578
mute_group_offset	seq64::Seq24SeqEventInput, 581
seq64::perform, 512	seq64::eventslots, 193
mute_group_tracks	seq64::mainwid, 331
seq64::perform, 504	seq64::perfnames, 456
mute_op_t	seq64::perfroll, 542
seq64::perform, 471	seq64::perftime, 555
mute_screenset	seq64::seqdata, 589
seq64::perform, 486	seq64::seqevent, 630
mutex	seq64::seqkeys, 642
seq64::mutex, 424	seq64::seqroll, 676
•	seq64::seqtime, 688
name	on_button_release_event
seq64::sequence, 707	seq64::AbstractPerfInput, 103
seq64::user_instrument, 774	seq64::FruityPerfInput, 204
seq64::user_midi_bus, 779	seq64::FruitySeqEventInput, 208
name_change_callback	seq64::FruitySeqRollInput, 210
seq64::seqedit, 606	seq64::Seq24PerfInput, 578
name_to_value	
seq64::editable event, 122	seq64::Seq24SeqEventInput, 581
new_current_sequence	seq64::eventslots, 193
seq64::seqmenu, 650	seq64::mainwid, 332
new file	seq64::perfnames, 456
seq64::mainwnd, 348	seq64::perfroll, 542
new_open_error_dialog	seq64::perftime, 556
seq64::mainwnd, 347	seq64::seqdata, 590
new_sequence	seq64::seqevent, 631
seq64::perform, 480	seq64::seqkeys, 642
seq64::seqmenu, 650	seq64::seqroll, 677
next	seq64::seqtime, 689
seq64::triggers, 769	on_delete_event
next_data_line	seq64::eventedit, 176
seq64::configfile, 113	seq64::mainwnd, 349
next_trigger	seq64::perfedit, 446
seq64::triggers, 769	seq64::seqedit, 610
normal action	on_enter_notify_event
seq64::seqroll, 675	seq64::seqkeys, 643
normalize	seq64::seqroll, 679
seq64::user settings, 790	on_expose_event
note_off_length	seq64::eventslots, 193
seq64::seqroll, 662	seq64::maintime, 321
·	seq64::mainwid, 331
note_off_margin	seq64::perfnames, 455
seq64::sequence, 743	seq64::perfroll, 542
number	seq64::perftime, 555
seq64::sequence, 702	seq64::seqdata, 589
off playing notes	seq64::seqevent, 630
off_playing_notes	seq64::seqkeys, 642
seq64::sequence, 737	seq64::seqroll, 676
off_queued	seq64::seqtime, 688
seq64::sequence, 709	on_focus_in_event
off_sequences	seq64::eventedit, 175
seq64::perform, 507	•
offset	seq64::eventslots, 194
seq64::trigger, 755	seq64::mainwid, 333
on_button_press_event	seq64::perfroll, 543
seq64::AbstractPerfInput, 103	seq64::seqedit, 610
seq64::FruityPerfInput, 203	seq64::seqevent, 632
seq64::FruitySeqEventInput, 207	seq64::seqroll, 677
seq64::FruitySeqRollInput, 210	on_focus_out_event

seq64::eventedit, 175	seq64::gui_drawingarea_gtk2, 231
seq64::eventslots, 194	seq64::gui_window_gtk2, 247
seq64::lfownd, 316	seq64::maintime, 320
seq64::mainwid, 333	seq64::mainwid, 331
seq64::perfroll, 543	seq64::perfedit, 445
seq64::seqedit, 610	seq64::perfnames, 455
seq64::seqevent, 632	seq64::perfroll, 541
seq64::seqroll, 678	seq64::perftime, 555
on_frame_down	seq64::seqdata, 589
seq64::eventslots, 194	seq64::seqedit, 610
on_frame_end	seq64::seqevent, 630
seq64::eventslots, 195	seq64::seqkeys, 642
on_frame_home	seq64::seqmenu, 653
seq64::eventslots, 195	seq64::seqroll, 676
on_frame_up	seq64::seqtime, 688
seq64::eventslots, 194	on_right_button_pressed
on_grouplearnchange	seq64::FruityPerfInput, 205
seq64::mainwnd, 349	on_scroll_event
seq64::performcallback, 530	seq64::eventslots, 194
on_key_press_event	seq64::perfnames, 457
seq64::eventedit, 175	seq64::perfroll, 542
seq64::keybindentry, 273	seq64::seqdata, 590
seq64::mainwnd, 349	seq64::seqedit, 610
seq64::perfedit, 445	seq64::seqkeys, 643
seq64::perfroll, 543	seq64::seqroll, 678
seq64::seqedit, 611	on_set_focus
seq64::seqevent, 632	seq64::eventedit, 175
seq64::seqroll, 678	seq64::seqedit, 610
on_key_release_event	on_size_allocate
seq64::mainwnd, 349	seq64::eventslots, 194
on_leave_notify_event	seq64::perfnames, 456
seq64::seqdata, 590	seq64::perfroll, 543
seq64::seqkeys, 643	seq64::perftime, 556
seq64::seqroll, 679	seq64::seqdata, 591
on_left_button_pressed	seq64::seqevent, 632
seq64::FruityPerfInput, 205	seq64::seqkeys, 644
on_motion_notify_event	seq64::seqroll, 679
seq64::AbstractPerfInput, 103	seq64::seqtime, 688
seq64::FruityPerfInput, 204	on_size_request
seq64::FruitySeqEventInput, 208	seq64::perfroll, 544
seq64::FruitySeqRollInput, 211	open_file
seq64::Seq24PerfInput, 579	seq64::mainwnd, 342
seq64::Seq24SeqEventInput, 582	open_performance_edit
seq64::mainwid, 332	seq64::mainwnd, 344
seq64::perfroll, 542	open_performance_edit_2
seq64::seqdata, 590	seq64::mainwnd, 345
seq64::seqevent, 631	operator<
seq64::seqkeys, 643	seq64::event, 141
seq64::seqroll, 677	seq64::event_list::event_key, 155
on_move_down	seq64::trigger, 753
seq64::eventslots, 194	operator=
on_move_up	seq64::automutex, 105
seq64::eventslots, 194	seq64::click, 108
on_queued	seq64::editable_event, 122
seq64::sequence, 710	seq64::editable_events, 132
on_realize	seq64::event, 141
seq64::eventedit, 175 seq64::eventslots, 193	seq64::event_list, 159 seq64::gui_drawingarea_gtk2, 220
364046v611131013, 133	56404gui_uiawiiigai6a_gin2, 220

seq64::keystroke, 308	seq64::midifile, 409
seq64::maintime, 320	parse_smf_1
seq64::rc_settings, 563	seq64::midifile, 409
seq64::sequence, 701	partial_assign
seq64::triggers, 760	seq64::sequence, 701
seq64::user_instrument, 773	pass_sysex
seq64::user_midi_bus, 778	seq64::rc_settings, 564, 567
seq64::user_settings, 790	paste
options	seq64::triggers, 766
seq64::keybindentry, 273	paste_selected
seq64::keys_perform, 297	seq64::sequence, 726
seq64::options, 427	paste_trigger
seq64::perform, 516	seq64::sequence, 719
seq64::rc_settings, 571	pattern_edit
options_dialog	seq64::keys_perform, 287
seq64::mainwnd, 346	pause
optionsfile	seq64::keys_perform, 286
seq64::keys_perform, 297	seq64::sequence, 738
seq64::optionsfile, 431	pause_key
seq64::perform, 516	seq64::perform, 493
seq64::rc_settings, 571	• •
orange	pause_playing
seq64::gui_palette_gtk2, 240	seq64::mainwnd, 344
output	seq64::perfedit, 445
seq64::jack_assistant, 256	seq64::perform, 492
output_func	perf
seq64::perform, 487	seq64::gui_drawingarea_gtk2, 221
output_thread_func	seq64::gui_window_gtk2, 246
seq64, 80	seq64::options, 427
•	perf_h_page_increment
seq64::perform, 517	seq64::user_settings, 796, 800
padded_height	perf_modify
seq64::font, 200	seq64::eventedit, 172
page movement	perf_v_page_increment
seq64::eventslots, 191	seq64::user_settings, 796, 801
page_topper	perfedit
seq64::eventslots, 192	seq64::perfedit, 439
pager index	seq64::perfnames, 457
seq64::eventslots, 184	seq64::perform, 516
paint	seq64::perfroll, 544
seq64::event, 149	seq64::perftime, 557
parent	perfnames
seq64::editable_event, 122	seq64::perfnames, 453
seq64::jack_assistant, 252	perform
parse	seq64::keys_perform, 297
seq64::configfile, 114	seq64::perform, 472
seq64::midifile, 407	seq64::sequence, 745
•	perfroll
seq64::optionsfile, 431	seq64::AbstractPerfInput, 104
seq64::userfile, 812	seq64::FruityPerfInput, 206
parse_command_line_options	
seq64, 72	seq64::Seq24PerfInput, 580
seq64::rc_settings, 571	seq64::perform, 516
parse_options_files	seq64::perfroll, 535
seq64, 72	perfroll_key_event
parse_prop_header	seq64::perform, 496
seq64::midifile, 410	perftime
parse_proprietary_track	seq64::perftime, 551
seq64::midifile, 411	pixel_to_tick
parse_smf_0	seq64::perftime, 554

play	seq64::midi_container, 371
seq64::mastermidibus, 362	pow2
seq64::midibus, 399	seq64::midifile, 411
seq64::perform, 509	ppqn
seq64::sequence, 713	seq64::mainwnd, 342
seq64::triggers, 761	seq64::midi_splitter, 387
play_change_callback	seq64::midi_timing, 391
seq64::seqedit, 606	seq64::midifile, 409
play_note_off	ppqn_is_valid
seq64::sequence, 737	seq64, 76
play_note_on	print
seq64::sequence, 737	seq64::event, 152
play_queue	seq64::event_list, 164
seq64::sequence, 713	seq64::mastermidibus, 359
playback_key_event	seq64::midibus, 399
seq64::perform, 497	seq64::sequence, 713
pointer_position	seq64::triggers, 761
seq64::keys_perform, 289	print_keys
poll_for_midi	seq64::rc_settings, 565, 568
seq64::mastermidibus, 360	print_triggers
pop_redo	seq64::perform, 481
seq64::sequence, 704	seq64::sequence, 713
seq64::triggers, 761	priority
pop_trigger_redo	seq64::rc_settings, 564, 567
seq64::perform, 498	private_bus
seq64::sequence, 704	seq64::user_settings, 802
pop_trigger_undo	private_instrument
seq64::perform, 498	seq64::user_settings, 802
seq64::sequence, 704	process_events
pop_undo	seq64::lash, 312
seq64::sequence, 704	progress_bar_colored
seq64::triggers, 761	seq64::user_settings, 796, 801
popup_event_menu	progress_bar_thick
seq64::seqedit, 608	seq64::user_settings, 796, 801
popup_menu	progress_color
seq64::perfedit, 444	seq64::gui_palette_gtk2, 238
seq64::seqedit, 608	prop_item_size
seq64::seqmenu, 651	seq64::midifile, 418
popup_midibus_menu	pulse_length_us
seq64::seqedit, 608	seq64, 67
popup_midich_menu	pulses_per_measure
seq64::seqedit, 609	seq64, 70
popup_sequence_menu	pulses_to_measurestring
seq64::seqedit, 608	seq64, 59
popup_tool_menu	pulses_to_midi_measures
seq64::seqedit, 608	seq64, 59
port_exit	pulses_to_string
seq64::mastermidibus, 362	seq64, 59
port_start	pulses_to_timestring
seq64::mastermidibus, 362	seq64, 60
position	push_quantize
seq64::jack_assistant, 255	seq64::sequence, 741
seq64::midi_container, 371	push_trigger_undo
position_increment	seq64::perform, 498
seq64::midi_container, 371	seq64::sequence, 704
position_jack	push_undo
seq64::perform, 507	seq64::sequence, 703
position_reset	seq64::triggers, 761

put	redraw_period_ms
seq64::midi_container, 370	seq64::gui_window_gtk2, 246
seq64::midi_list, 381	redraw_progress
seq64::midi_vector, 394	seq64::perfroll, 536
put_event_on_bus	remove
seq64::sequence, 743	seq64::editable_events, 134
	seq64::event_list, 160
q_rec_change_callback	seq64::sequence, 744, 745
seq64::seqedit, 606	seq64::triggers, 763
quantize_events	remove_all
seq64::sequence, 740	seq64::sequence, 745
query_save_changes	remove_marked
seq64::mainwnd, 346	seq64::event_list, 163
queue	seq64::sequence, 736
seq64::keys_perform, 283	remove_selected
quit	seq64::sequence, 736
seq64::gui_assistant, 213	seq64::triggers, 766
seq64::gui_assistant_gtk2, 215	render number
seq64::gui_window_gtk2, 246	seq64::seqdata, 588
	render_string
rc	
seq64, 81	seq64::gui_drawingarea_gtk2, 225
rc_settings	render_string_on_drawable
seq64::rc_settings, 562	seq64::font, 199
read_byte	render_string_on_pixmap
seq64::midifile, 413	seq64::gui_drawingarea_gtk2, 226
read_byte_array	replace
seq64::midifile, 414	seq64::editable_events, 134
read_long	seq64::keys_perform, 283
seq64::midifile, 413	reposition
read_seq_number	seq64::perform, 479
seq64::midifile, 416	reset
read_short	seq64::mainwid, 327
seq64::midifile, 413	seq64::perftime, 552
read_track_name	seq64::seqdata, 586
seq64::midifile, 415	seq64::seqevent, 626
read varinum	seq64::seqkeys, 641
seq64::midifile, 413	seq64::seqroll, 665
record_change_callback	seq64::seqtime, 687
seq64::seqedit, 606	seq64::sequence, 738
red	reset_draw_marker
seq64::gui_palette_gtk2, 240	seq64::sequence, 738
redo	reset_draw_trigger_marker
seq64::perfedit, 444	seq64::sequence, 738
redo callback	seq64::triggers, 769
seq64::seqedit, 607	reset_sequences
redraw	seq64::perform, 508
seq64::mainwid, 327	restart sysex
seq64::perfnames, 455	seq64::event, 148
seq64::seqdata, 586	restore_playing_state
seq64::seqevent, 626	seq64::perform, 488
seq64::seqmenu, 652	RevSlotMap
·	seq64::keys_perform, 281
seq64::seqroll, 665	reveal_alsa_ports
seq64::seqtime, 687	
redraw_dirty_sequences	seq64::rc_settings, 565, 568
seq64::perfnames, 454	rewind
seq64::perfroll, 537	seq64::keys_perform, 288, 289
redraw_events	seq64::perfedit, 441
seq64::seqroll, 665	seq64::perform, 478

s_arg_list	save_events
seq64, 95	seq64::editable_events, 132
s_build_chord_generator	seq64::eventslots, 188
seq64, 96	save_file
s_build_edit_highlight	seq64::mainwnd, 348
seq64, 97	save_playing_state
s_build_follow_progress	seq64::perform, 488
seq64, 97	save_user_config
s_build_highlight_empty	seq64::user_settings, 797
seq64, 96	scale_lfo_change
s_build_jack_session	seq64::lfownd, 315
seq64, 96	screenset_dn
s_build_jack_support	seq64::keys_perform, 285
seq64, 96	screenset_up
s_build_lash_support	seq64::keys_perform, 284
seq64, 96	scroll_hadjust
s_build_midi_vector	seq64::gui_drawingarea_gtk2, 230
seq64, 97	seq64::gui_window_gtk2, 246
s_build_pause_support	scroll hset
seq64, 96	seq64::gui_drawingarea_gtk2, 231
s_build_solid_grid	seq64::gui_window_gtk2, 247
seq64, 97	scroll_offset_x
s_build_timesig_tempo	seq64::seqroll, 674
seq64, 97	scroll_offset_y
s_build_use_event_map	seq64::seqroll, 674
seq64, 96	scroll_vadjust
s_character_mapping	seq64::gui_drawingarea_gtk2, 230
seq64, 98	seq64::gui_window_gtk2, 246
s_event_editor	scroll_vset
seq64, 96	seq64::gui_drawingarea_gtk2, 231
s_global_lash_driver	seq64::gui_window_gtk2, 247
seq64, 98	select
s handlesize	seq64::event, 150
seq64, 99	seq64::triggers, 764
s_help_1a	select action
seq64, 95	seq64::seqroll, 676
s_help_1b	select action e
seq64, 95	seq64::sequence, 700
s_help_2	select_all
seq64, 95	seq64::event list, 164
s_help_3	seq64::sequence, 725
seq64, 96	select_all_notes
s_help_4	seq64::sequence, 724
seq64, 96	select_and_mute_group
s jitter amount	seq64::perform, 504
seq64, 99	select_even_or_odd_notes
s_seq32_jack_support	seq64::sequence, 724
seq64, 97	select event
s_seq32_menu_buttons	seq64::eventslots, 188
seq64, 98	select_event_handle
s_seq32_transport	seq64::sequence, 723
seq64, 97	select_events
s_seq32_transpose	seq64::sequence, 722, 723
s_seq52_transpose seq64, 97	
•	select_fg_bg_colors seq64::mainwid, 331
s_statistics_support seq64, 97	select_group_mute
•	
s_strip_empty_mutes	seq64::perform, 505
seq64, 97	select_linked

anged vanguages 704	a music coolea EG
seq64::sequence, 724	c_music_scales, 56 c_musickey, 90
select_note_events	c musicscale, 90
seq64::sequence, 722	-
select_trigger	c_mutegroups, 90
seq64::sequence, 716	c_notes, 89
selected	c_perf_bp_mes, 90
seq64::trigger, 755	c_perf_bw, 90
selected_trigger_end	c_scales_policy, 92
seq64::sequence, 720	c_scales_text, 93
selected_trigger_start	c_scales_transpose_dn, 93
seq64::sequence, 719	c_scales_transpose_up, 92
selecting	c_status_queue, 98
seq64::seqroll, 675	c_status_replace, 98
Seq24PerfInput	c_status_snapshot, 98
seq64::Seq24PerfInput, 578	c_timesig, 89
seq64::perfroll, 544	c_transpose, 90
seq64::triggers, 771	c_triggers, 89
Seq24SeqEventInput	c_triggers_new, 90
seq64::Seq24SeqEventInput, 581	choose_ppqn, 81
seq64::seqevent, 633	clamp, 83, 84
seq64, 41	clock_e, 56
adjustment_dummy, 83	clock_tick_duration_bogus, 69
beats_per_minute_from_tempo_us, 66	clock_ticks_from_ppqn, 69
build_details, 73	create_lash_driver, 79
bussbyte, 53	delete_lash_driver, 80
c_backsequence, 90	delta_time_us_to_ticks, 68
c_bpmtag, 89	double_ticks_from_ppqn, 70
c_chord_number, 94	draw_type_t, 57
c_chord_size, 94	EVENT_AFTERTOUCH, 84
c_chord_table, 94	EVENT_ANY, 84
c_chord_table_text, 94	EVENT_CHANNEL_PRESSURE, 85
c_chord_text, 94	EVENT_CLEAR_CHAN_MASK, 87
c_controller_names, 84	EVENT_CONTROL_CHANGE, 85
c_interval_text, 94	EVENT_GET_CHAN_MASK, 87
c_key_text, 94	EVENT_MIDI_ACTIVE_SENS, 87
c_mainwid_x, 99	EVENT_MIDI_CLOCK, 86
c_mainwid_y, 99	EVENT_MIDI_CONTINUE, 86
c_max_busses, 95	EVENT_MIDI_META, 87
c_max_instruments, 94	EVENT_MIDI_QUARTER_FRAME, 85
c_midi_control_bpm_dn, 91	EVENT_MIDI_RESET, 87
c_midi_control_bpm_up, 91	EVENT_MIDI_SONG_F4, 86
c_midi_control_mod_glearn, 91	EVENT_MIDI_SONG_F5, 86
c_midi_control_mod_gmute, 91	EVENT_MIDI_SONG_F9, 86
c_midi_control_mod_queue, 91	EVENT_MIDI_SONG_FD, 87
c_midi_control_mod_replace, 91	EVENT_MIDI_SONG_POS, 85
c_midi_control_mod_snapshot, 91	EVENT_MIDI_SONG_SELECT, 85
c_midi_control_play_ss, 92	EVENT_MIDI_START, 86
c_midi_control_ss_dn, 91	EVENT_MIDI_STOP, 86
c_midi_control_ss_up, 91	EVENT_MIDI_SYSEX_CONTINUE, 86
c_midi_controls, 92	EVENT_MIDI_SYSEX_END, 86
c_midi_track_ctrl, 90	EVENT_MIDI_SYSEX, 85
c_midibus, 88	EVENT_MIDI_TUNE_SELECT, 86
c_midibus_input_size, 88	EVENT_NOTE_OFF, 84
c_midibus_output_size, 88	EVENT_NOTE_ON, 84
c_midibus_sysex_chunk, 88	EVENT_NULL_CHANNEL, 87
c_midich, 89	EVENT_PITCH_WHEEL, 85
c_midiclocks, 89	EVENT_PROGRAM_CHANGE, 85
c_midictrl, 90	EVENT_STATUS_BIT, 84

EVENTO ALL OZ	- build - dia bindinda 07
EVENTS_ALL, 87	s_build_edit_highlight, 97
EVENTS_UNSELECTED, 87	s_build_follow_progress, 97
edit_action_t, 57	s_build_highlight_empty, 96
extract_timing_numbers, 58	s_build_jack_session, 96
FF_RW_timeout, 83	s_build_jack_support, 96
file_access, 74	s_build_lash_support, 96
file_accessible, 75	s_build_midi_vector, 97
file_executable, 75	s_build_pause_support, 96
file_exists, 74	s_build_solid_grid, 97
file_is_directory, 75	s_build_timesig_tempo, 97
file_readable, 74	s_build_use_event_map, 96
file_writable, 74	s_character_mapping, 98
font_render, 82	s_event_editor, 96
g_rc_settings, 98	s_global_lash_driver, 98
g_user_settings, 98	s_handlesize, 99
get_current_jack_position, 78	s_help_1a, 95
gs_mainwid_pointer, 99	s_help_1b, 95
gs_perfedit_pointer_0, 99	s_help_2, 95
gs_perfedit_pointer_1, 99	s_help_3, 96
help_check, 71	s_help_4, 96
input_thread_func, 81	s_jitter_amount, 99
interaction_method_t, 56	s_seq32_jack_support, 97
invalid_key, 79	s_seq32_menu_buttons, 98
is_null_midipulse, 80	s_seq32_transport, 97
jack_process_callback, 78	s_seq32_transpose, 97
jack_session_callback, 78	s_statistics_support, 97
jack_shutdown_callback, 77	s_strip_empty_mutes, 97
jack_sync_callback, 76	seq_event_type_t, 55
jack_timebase_callback, 77	seq_modifier_t, 54
keyval_name, 79	seq_scroll_direction_t, 55
keyval_normalize, 79	shorten_file_spec, 64
lash_driver, 80	string is void, 64
log2_time_sig_value, 65	string_not_void, 64
long_options, 95	string to midibyte, 62
make_directory, 76	string_to_pulses, 62
make_section_name, 82	strings_match, 65
measures_to_ticks, 70	tempo_to_us, 67
measurestring_to_pulses, 61	tempo_to_us, 67 tempo us from beats per minute, 67
midi_measures_to_pulses, 61	tempo_us_to_bytes, 66
midibyte, 53	ticks_to_delta_time_us, 68
midilong, 53	timestring_to_pulses, 61
midipulse, 54	to string, 73
midishort, 53	update_mainwid_sequences, 83
min, 82	update_mainwid_sequences, 83
mouse action e, 57	. – .
:	usr, 81
output_thread_func, 80	versiontext, 95
parse_command_line_options, 72	wave_func, 71
parse_options_files, 72	wave_type_t, 54
ppqn_is_valid, 76	write_options_files, 73
pulse_length_us, 67	zoom_power_of_2, 66
pulses_per_measure, 70	seq64::AbstractPerfInput, 101
pulses_to_measurestring, 59	~AbstractPerfInput, 102
pulses_to_midi_measures, 59	AbstractPerfInput, 102
pulses_to_string, 59	activate_adding, 103
pulses_to_timestring, 60	handle_motion_key, 103
rc, 81	is_adding, 103
s_arg_list, 95	is_adding_pressed, 104
s_build_chord_generator, 96	m_adding, 104

m_adding_pressed, 104	seq64::click, 106
on_button_press_event, 103	button, 109
on_button_release_event, 103	click, 107
on_motion_notify_event, 103	is_left, 108
perfroll, 104	is_middle, 108
set_adding, 103	is_press, 108
set_adding_pressed, 104	is_right, 108
seq64::FruityPerfInput, 202	m_button, 110
activate_adding, 206	m_is_press, 109
FruityPerfInput, 203	m_modifier, 110
handle_motion_key, 206	m_x, 109
m_current_x, 206	m_y, 109
m_current_y, 206	mod_control, 109
on_button_press_event, 203	mod_control_shift, 109
on_button_release_event, 204	mod_super, 109
on_left_button_pressed, 205	modifier, 109
on_motion_notify_event, 204	operator=, 108
on_right_button_pressed, 205	x, 108
perfroll, 206	y, 109
update_mouse_pointer, 204	seq64::condition_var, 110
seq64::FruitySeqEventInput, 206	condition_var, 111
FruitySeqEventInput, 207	m_cond, 112
m_is_drag_pasting, 209	signal, 111
m_is_drag_pasting_start, 209	sm_cond, 112
m_justselected_one, 209	wait, 111
on_button_press_event, 207	seq64::configfile, 112
on_button_release_event, 208	\sim configfile, 113
on_motion_notify_event, 208	configfile, 113
update_mouse_pointer, 207	line_after, 114
seq64::FruitySeqRollInput, 209	m_d, 115
FruitySeqRollInput, 210	m_line, 115
m_drag_paste_start_pos, 211	m_name, 115
m_erase_painting, 211	next_data_line, 113
on button press event, 210	parse, 114
on_button_release_event, 210	write, 114
on_motion_notify_event, 211	seq64::editable event, 115
update mouse pointer, 210	~editable_event, 121
seq64::Seq24PerfInput, 577	analyze, 125
activate_adding, 579	category, 122, 123
handle_motion_key, 579	category string, 123
m effective tick, 580	category_t, 119
on_button_press_event, 578	channel string, 125
on_button_release_event, 578	data_string, 125
on_motion_notify_event, 579	editable event, 120, 121
perfroll, 580	format_timestamp, 124
Seq24PerfInput, 578	m_category, 127
seq64::Seq24SeqEventInput, 580	m_format_timestamp, 127
m_adding, 582	m_name_category, 127
on_button_press_event, 581	m_name_channel, 128
on button release event, 581	m_name_data, 128
on_motion_notify_event, 582	m name meta, 128
Seq24SeqEventInput, 581	m_name_seqspec, 128
set_adding, 581	m_name_status, 128
set_adding, 561 seq64::automutex, 104	
~automutex, 105	m_name_timestamp, 127
	m_parent, 127
automutex, 105	meta_string, 125
m_safety_mutex, 106	name_to_value, 122
operator=, 105	operator=, 122

parent, 122	get_channel, 142
seqspec_string, 125	get_data, 147
set_status_from_string, 124	get_linked, 149
sm_category_arrays, 127	get_note, 150
sm_category_names, 126	get_note_velocity, 151
sm_channel_event_names, 126	get_rank, 152
sm_meta_event_names, 126	get_status, 147
sm_prop_event_names, 127	get_sysex, 148, 149
sm_system_event_names, 126	get_sysex_size, 149
status_string, 125	get_timestamp, 142
stock_event_string, 125	increment_data1, 147
time_as_measures, 124	increment_data2, 148
time_as_minutes, 124	is_channel_msg, 143
time_as_pulses, 124	is_desired_cc_or_not_cc, 144
timestamp, 123	is_linked, 149
timestamp_format_t, 120	is_marked, 150
timestamp_string, 123	is_note, 151
value_to_name, 121	is_note_msg, 144
seq64::editable_event::name_value_t, 424	is_note_off, 151
event_name, 425	is_note_off_recorded, 152
event_value, 425	is_note_on, 151
seq64::editable_events, 128	is_one_byte_msg, 143
\sim editable_events, 131	is_painted, 150
add, 133, 134	is_selected, 150
begin, 133	is_strict_note_msg, 144
clear, 134	is_two_byte_msg, 143
const_iterator, 131	link, 149
count, 133	m_channel, 153
current_event, 134, 135	m_data, 153
dref, 133	m_has_link, 153
editable_events, 131	m_linked, 153
end, 133	m_marked, 153
Events, 130	m_painted, 154
events, 132	m_selected, 153
EventsPair, 130	m_status, 152
eventslots, 135	m_sysex, 153
iterator, 130	m_sysex_size, 153
Key, 130	m_timestamp, 152
load_events, 132	make_clock, 150
m_current_event, 135	mark, 150
m_events, 135	mod_timestamp, 145
m_midi_parameters, 135	operator<, 141
m_sequence, 135	operator=, 141
operator=, 132	paint, 149
remove, 134	print, 152
replace, 134	restart_sysex, 148
save_events, 132	select, 150
string_to_pulses, 132	set_channel, 146
timing, 132	set_data, 147
seq64::event, 136	set_note, 150
\sim event, 141	set_note_velocity, 151
append_sysex, 148	set_status, 145, 146
check_channel, 142	set_status_keep_channel, 146
clear_link, 149	set_sysex_size, 149
data, 150	set_timestamp, 142
decrement_data1, 147	SysexContainer, 140
decrement_data2, 148	transpose_note, 151
event, 140	unmark, 150

unpaint, 149	handle_insert, 174
unselect, 150	handle_modify, 174
seq64::event_list, 155	handle_save, 174
\sim event_list, 158	m_bottbox, 177
add, 159	m_button_cancel, 177
any_selected_notes, 163	m_button_del, 177
begin, 159	m_button_ins, 177
clear, 160	m_button_modify, 177
clear_links, 162	m_button_save, 177
const_iterator, 158	m_editbox, 177
count, 159	m_entry_ev_data_0, 179
count_selected_events, 164	m_entry_ev_data_1, 179
count_selected_notes, 163	m_entry_ev_name, 179
dref, 161	m_entry_ev_timestamp, 178
editable_events, 165	m_eventslots, 176
empty, 159	m_have_focus, 179
end, 159	m_htopbox, 176
event_list, 158	m_label_category, 178
Events, 158	m_label_channel, 178
events, 164	m_label_ev_count, 178
EventsPair, 158	m_label_modified, 178
is_modified, 160	m_label_ppqn, 178
iterator, 158	m label right, 179
link new, 162	m_label_seq_name, 178
m_events, 165	m_label_spacer, 178
m_is_modified, 165	m_label_time_fmt, 179
mark all, 163	m_label_time_sig, 178
mark_out_of_range, 162	m_optsbox, 177
mark_selected, 162	m_rightbox, 177
merge, 161	m_seq, 179
midi container, 165	m showbox, 177
midi_splitter, 165	m_table, 176
operator=, 159	m_vadjust, 176
print, 164	m vscroll, 176
remove, 160	on_delete_event, 176
remove_marked, 163	on_focus_in_event, 175
select_all, 164	on_focus_out_event, 175
sequence, 165	on_key_press_event, 175
unmark_all, 163	on_realize, 175
unmodify, 160	on_set_focus, 175
unpaint_all, 163	perf_modify, 172
unselect_all, 164	set_dirty, 172
verify_and_link, 162	set_event_category, 171
seq64::event_list::event_key, 154	set_event_data_0, 172
event_key, 154, 155	set_event_data_1, 172
m_rank, 155	set_event_name, 172
m_timestamp, 155	set_event_timestamp, 172
operator<, 155	set_seq_count, 171
seq64::eventedit, 166	set_seq_ppqn, 171
\sim eventedit, 170	set_seq_time_sig, 171
change_focus, 173	set_seq_title, 171
close_out, 174	v_adjustment, 173
enqueue_draw, 171	seq64::eventslots, 180
eventedit, 169	∼eventslots, 184
eventslots, 176	change_vert, 191
handle_cancel, 174	convert_y, 190
handle_close, 174	current_index, 184
handle_delete, 174	decrement_bottom, 193

degrament current 102	coasa-font 107
decrement_current, 192 decrement_top, 192	seq64::font, 197 char_height, 200
delete current event, 186	char_width, 199
draw event, 190	Color, 198
draw events, 191	font, 199
enqueue_draw, 190	init, 199
event_count, 184	m_b_on_c_pixmap, 201
eventedit, 195	m_b_on_y_pixmap, 201
eventslots, 184	m_black_pixmap, 201
increment_bottom, 193	m_c_on_b_pixmap, 201
increment current, 192	m_cell_h, 200
increment top, 192	m cell w, 200
insert_event, 185, 186	m_clip_mask, 202
line count, 184	m_font_h, 200
line_increment, 184	m_font_w, 200
line_maximum, 184	m_offset, 200
load_events, 185	m padded h, 200
m_bottom_iterator, 197	m pixmap, 201
m_char_w, 195	m use new font, 200
m_current_index, 196	m_white_pixmap, 201
m_current_iterator, 197	m_y_on_b_pixmap, 201
m event container, 195	padded_height, 200
m event count, 196	render_string_on_drawable, 199
m_line_count, 196	seq64::gui_assistant, 212
m_line_maximum, 196	∼gui_assistant, 213
m_line_overlap, 196	gui_assistant, 213
m_pager_index, 197	jack_idle_connect, 213
m_parent, 195	keys, 213
m_seq, 195	lash_timeout_connect, 213
m_setbox_w, 195	m_keys_perform, 214
m slots chars, 195	quit, 213
m_slots_x, 196	seq64::gui_assistant_gtk2, 214
m_slots_y, 196	∼gui_assistant_gtk2, 215
m_top_index, 196	gui_assistant_gtk2, 215
m_top_iterator, 196	jack_idle_connect, 215
modify_current_event, 187	lash_timeout_connect, 215
on_button_press_event, 193	quit, 215
on_button_release_event, 193	sm_internal_keys, 216
on_expose_event, 193	seq64::gui_drawingarea_gtk2, 216
on_focus_in_event, 194	\sim gui_drawingarea_gtk2, 220
on_focus_out_event, 194	clear_window, 221
on_frame_down, 194	current_x, 220
on_frame_end, 195	current_y, 220
on_frame_home, 195	draw_drawable, 230
on_frame_up, 194	draw_line, 221, 223-225
on_move_down, 194	draw_line_on_pixmap, 223
on_move_up, 194	draw_normal_rectangle_on_pixmap, 229
on_realize, 193	draw_rectangle, 226-228
on_scroll_event, 194	draw_rectangle_on_pixmap, 229
on_size_allocate, 194	drop_x, 220
page_movement, 191	drop_y, 221
page_topper, 192	force_draw, 221
pager_index, 184	gtk_drawarea_init, 231
save_events, 188	gui_drawingarea_gtk2, 219, 220
select_event, 188	m_background, 232
set_current_event, 185	m_current_x, 233
set_text, 188	m_current_y, 233
top_index, 184	m_drop_x, 233

m_drop_y, 233	m_dk_cyan, 242
m_foreground, 232	m_dk_green, 241
m_gc, 232	m_dk_grey, 242
m_hadjust, 232	m_dk_magenta, 242
m_mainperf, 232	m_dk_orange, 241
m_pixmap, 232	m_dk_red, 241
m_vadjust, 232	m_fg_color, 243
m_window, 232	m_green, 242
m_window_x, 233	m_grey, 242
m_window_y, 233	m_is_inverse, 241
on_realize, 231	m_line_color, 243
operator=, 220	m_lt_grey, 243
perf, 221	m_orange, 242
render_string, 225	m_progress_color, 243
render_string_on_pixmap, 226	m_red, 242
scroll_hadjust, 230	m_white, 242
scroll_hset, 231	m_wht_key, 243
scroll_vadjust, 230	m_wht_paint, 243
scroll_vset, 231	m_yellow, 242
set_current_drop_x, 231	orange, 240
set_current_drop_y, 231	progress_color, 238
set_line, 221	red, 240
window_x, 220	white, 239
window_y, 220	white_key, 240
seq64::gui_drawingarea_gtk2::rect, 576	white_paint, 240
height, 576	yellow, 240
width, 576	seq64::gui_window_gtk2, 244
x, 576	\sim gui_window_gtk2, 245
y, 576	gui_window_gtk2, 245
seq64::gui_palette_gtk2, 234	is_realized, 246
\sim gui_palette_gtk2, 238	m_is_realized, 248
bg_color, 240, 241	m_mainperf, 247
black, 238	m_redraw_period_ms, 248
black_key, 240	m_window_x, 247
black_paint, 240	m_window_y, 247
blue, 240	on_realize, 247
Color, 237	perf, 246
dark_blue, 239	quit, 246
dark_cyan, 239	redraw_period_ms, 246
dark_green, 239	scroll_hadjust, 246
dark_grey, 239	scroll_hset, 247
dark_magenta, 239	scroll_vadjust, 246
dark_orange, 239	scroll_vset, 247
dark_red, 239	seq64::jack_assistant, 248
fg_color, 241	\sim jack_assistant, 252
green, 240	client, 259
grey, 239	client_name, 259
gui_palette_gtk2, 238	client_open, 260
is_inverse, 238	client_uuid, 259
light_grey, 239	deinit, 254
line_color, 238	error_message, 260
load_inverse_palette, 238	get_beat_width, 253
m_bg_color, 243	get_beats_per_measure, 253
m_black, 241	get_beats_per_minute, 253
m_blk_key, 243	get_follow_transport, 258
m_blk_paint, 243	get_jack_client_info, 261
m_blue, 242	get_jack_mode, 258
m_dk_blue, 241	get_jack_pos, 257
	- - - ·

get_jack_stop_tick, 258	toggle_jack_mode, 257
get_jack_tick, 257	toggle_song_start_mode, 258
get_ppqn, 252	transport_not_starting, 254
info_message, 259	transport_state, 254
init, 254	seq64::jack_scratchpad, 268
is_master, 252	js_clock_tick, 269
is_running, 252	js_current_tick, 269
jack_assistant, 252	js_delta_tick_frac, 270
jack_frame_rate, 258	js_dumping, 270
jack_process_callback, 263	js_init_clock, 270
jack_session_callback, 265	js_jack_stopped, 269
jack_shutdown_callback, 263	js_looping, 270
jack_sync_callback, 264	js_playback_mode, 270
jack_timebase_callback, 264	js_ticks_converted, 270
m_beat_width, 268	js_ticks_converted_last, 270
m beats per measure, 268	js ticks delta, 270
m_beats_per_minute, 268	js_total_tick, 269
m follow transport, 268	seq64::jack status pair t, 270
m jack client, 266	jf_bit, 271
m_jack_client_name, 266	jf_meaning, 271
m_jack_client_uuid, 266	seg64::keybindentry, 271
	• •
m_jack_frame_current, 266	keybindentry, 272
m_jack_frame_last, 267	m_key, 273
m_jack_frame_rate, 267	m_perf, 273
m_jack_master, 267	m_slot, 273
m_jack_parent, 266	m_type, 273
m_jack_pos, 267	on_key_press_event, 273
m_jack_running, 267	options, 273
m_jack_stop_tick, 268	set, 273
m_jack_tick, 267	type, 272
m_jack_transport_state, 267	seq64::keys_perform, 274
m_jack_transport_state_last, 267	\sim keys_perform, 281
m_jsession_ev, 267	at_bpm_dn, 293
m_ppqn, 268	at_bpm_up, <mark>293</mark>
m_toggle_jack, 268	at_event_edit, 296
output, 256	at_fast_forward, 295
parent, 252	at_follow_transport, 295
position, 255	at_group_learn, 294
session_event, 255	at_group_off, 294
set_beat_width, 253	at_group_on, 294
set_beats_per_measure, 253	at_keep_queue, 293
set_beats_per_minute, 253	at_menu_mode, 295
set_follow_transport, 258	at_pattern_edit, 296
set_jack_mode, 258	at_pause, 295
set_jack_running, 259	at_pointer_position, 296
set_jack_stop_tick, 258	at_queue, 293
set position, 263	at_replace, 293
set_ppqn, 257	at_rewind, 295
set_start_from_perfedit, 259	at_screenset_dn, 294
show_position, 261	at_screenset_up, 294
show_statuses, 261	at_set_playing_screenset, 294
sm_status_pairs, 266	at_show_ui_sequence_key, 296
song_start_mode, 258	at_show_ui_sequence_number, 296
start, 255	at_snapshot_1, 294
stop, 255	at_snapshot_1, 294 at_snapshot_2, 294
sync, 262	at_snapshot_2, 294 at_song_mode, 295
tick_multiplier, 259	
toggle_follow_transport, 258	at_start, 295 at_stop, 296
toggio_ionow_transport, 200	αι_σιορ, 200

at_tap_bpm, 296	optionsfile, 297
at_toggle_jack, 295	pattern_edit, 287
at_toggle_mutes, 296	pause, 286
bpm_dn, 282, 283	perform, 297
bpm_up, 282	pointer_position, 289
event_edit, 287	queue, 283
fast_forward, 288	replace, 283
follow_transport, 288	RevSlotMap, 281
get_key_events, 290	rewind, 288, 289
get_key_events_rev, 290	screenset_dn, 285
get_key_groups, 290	screenset_up, 284
get_key_groups_rev, 291	set_all_key_events, 292
get_keys, 282	set_all_key_groups, 292
group_learn, 286	set_key_event, 292
group_off, 286	set_key_group, 293
group_on, 285	set_keys, 282
keep_queue, 283	set_playing_screenset, 285
key_name, 292	show_ui_sequence_key, 290
keys_perform, 281	show_ui_sequence_number, 290
lookup_keyevent_key, 291	SlotMap, 281
lookup_keyevent_seq, 291	snapshot_1, 284
lookup_keygroup_group, 291	snapshot_2, 284
lookup_keygroup_key, 291	song_mode, 288
m_key_bpm_dn, 298	start, 286
m_key_bpm_up, 298	stop, 287
m_key_event_edit, 300	tap_bpm, 289
m_key_events, 297	toggle_jack, 289
m_key_events_rev, 297	toggle_mutes, 289
m_key_fast_forward, 300	seq64::keys_perform_gtk2, 301
m_key_follow_transport, 300	~keys_perform_gtk2, 302
m_key_group_learn, 299	key_name, 302
m_key_group_off, 299	keys perform gtk2, 302
m_key_group_on, 299	set_all_key_events, 302
m_key_groups, 297	set_all_key_groups, 302
m_key_groups_rev, 298	seq64::keys perform transfer, 303
m_key_keep_queue, 298	kpt_bpm_dn, 303
m_key_menu_mode, 299	kpt bpm up, 303
m_key_pattern_edit, 300	kpt event edit, 305
m_key_pause, 299	kpt_fast_forward, 306
m_key_pointer_position, 300	kpt_follow_transport, 306
m_key_queue, 298	kpt_group_learn, 304
m_key_replace, 298	kpt_group_off, 304
m_key_rewind, 300	kpt_group_on, 304
m key screenset dn, 299	kpt_keep_queue, 304
m_key_screenset_up, 298	kpt_menu_mode, 306
m_key_set_playing_screenset, 299	kpt_pattern_edit, 305
m_key_show_ui_sequence_key, 297	kpt pause, 305
m_key_show_ui_sequence_number, 297	kpt_pointer_position, 306
m_key_snapshot_1, 298	kpt_queue, 304
m_key_snapshot_2, 298	kpt_replace, 304
m_key_song_mode, 299	kpt_rewind, 306
m_key_start, 299	kpt_screenset_dn, 304
m_key_stop, 300	kpt_screenset_up, 304
m_key_tap_bpm, 300	kpt_screenset_up, 304 kpt_set_playing_screenset, 304
m_key_toggle_jack, 299	kpt_show_ui_sequence_key, 305
m_key_toggle_mutes, 300	kpt_snow_ui_sequence_number, 305
menu_mode, 288	kpt_snow_ui_sequence_number, 303
options, 297	kpt_snapshot_1, 304 kpt_snapshot_2, 305

	1 1 1 1 004
kpt_song_mode, 305	m_box_height, 321
kpt_start, 305	m_box_less_pill, 322
kpt_stop, 305	m_box_width, 321
kpt_tap_bpm, 305	m_flash_height, 322
kpt_toggle_jack, 306	m_flash_width, 322
kpt_toggle_mutes, 306	m_flash_x, 322
seq64::keystroke, 306	m_pill_width, 321
is, 309	m_ppqn, 322
is_delete, 309	m_tick, 322
is_letter, 309	maintime, 320
is_press, 308	mainwnd, 321
key, 309	on_expose_event, 321
keystroke, 308	on_realize, 320
m_is_press, 310	operator=, 320
m_key, 310	seq64::mainwid, 323
m_modifier, 310	\sim mainwid, 326
mod_control, 310	calculate_base_sizes, 330
mod_control_shift, 310	draw_marker_on_sequence, 328
mod_super, 310	draw_pixmap_on_window, 327
modifier, 310	draw_sequence_on_pixmap, 329
operator=, 308	draw_sequence_pixmap_on_window, 329
shift_lock, 309	draw_sequences_on_pixmap, 329
seq64::lash, 311	fill_background_window, 327
handle_config, 313	m_button_down, 333
handle_event, 312	m_last_playing, 334
init, 312	m_last_tick_x, 334
lash, 312	m_mainwid_border, 335
m_client, 313	m_mainwid_spacing, 335
m_is_lash_supported, 313	m_mainwid_x, 335
m_lash_args, 313	m_mainwid_y, 335
m_perform, 313	m_mainwnd_cols, 334
process_events, 312	m_mainwnd_rows, 334
set_alsa_client_id, 312	m_max_sets, 335
start, 312	m_moving, 334
seq64::lfownd, 314	m_moving_seq, 333
\sim lfownd, 315	m_old_seq, 334
Ifownd, 315	m_progress_height, 336
m_hbox, 316	m_screenset, 334
m_phase, 317	m_screenset_offset, 336
m_range, 317	m_screenset_slots, 335
m_scale_phase, 316	m_seqarea_seq_x, 335
m_scale_range, 316	m_seqarea_seq_y, 335
m_scale_speed, 316	m_seqarea_x, 334
m_scale_value, 316	m_seqarea_y, 334
m_scale_wave, 316	m_text_size_x, 335
m_seq, 316	m_text_size_y, 335
m_seqdata, 316	mainwid, 326
m_speed, 317	mainwnd, 333
m_value, 316	on_button_press_event, 331
m_wave, 317	on_button_release_event, 332
on_focus_out_event, 316	on_expose_event, 331
scale_lfo_change, 315	on_focus_in_event, 333
toggle_visible, 315	on_focus_out_event, 333
seq64::maintime, 317	on_motion_notify_event, 332
\sim maintime, 320	on_realize, 331
idle_progress, 320	redraw, 327
m_bar_width, 321	reset, 327
m_beat_width, 321	select_fg_bg_colors, 331

	seq_from_xy, 330	m_spinbutton_ss, 352
	seq_set_and_edit, 328	m_timeout_connect, 353
	seq_set_and_eventedit, 328	m_tooltips, 350
	set_screenset, 327	mainwnd, 341
	timeout, 330	new_file, 348
	update_mainwid_sequences, 333	new_open_error_dialog, 347
	update_markers, 328	on_delete_event, 349
	update_sequences_on_window, 327	on_grouplearnchange, 349
	valid_sequence, 329	on_key_press_event, 349
seq	64::mainwnd, 336	on_key_release_event, 349
	∼mainwnd, 342	open_file, 342
	about_dialog, 346	open_performance_edit, 344
	adj_callback_bpm, 343	open_performance_edit_2, 345
	adj_callback_ss, 342	options_dialog, 346
	apply_song_transpose, 345	pause_playing, 344
	build_info_dialog, 346	ppqn, 342
	choose_file, 348	query_save_changes, 346
	edit callback notepad, 343	save_file, 348
	edit field has focus, 348	sequence_key, 345
	enregister_perfedits, 345	set_play_image, 343
	file exit, 347	set_song_mute, 346
	file_import_dialog, 346	set_songlive_image, 343
	file new, 345	signal_action, 348
	file open, 345	start_playing, 344
	file_save, 346	stop_playing, 344
	file_save_as, 347	timer_callback, 343
	handle signal, 342	toLower, 345
	install_signal_handlers, 348	toggle_playing, 344
	is_save, 348	update_window_title, 345
	learn_toggle, 344	seq64::mastermidibus, 353
	m_adjust_bpm, 352	•
	iii adjust bpiii, 332	\sim mastermidibus, 356
		\sim mastermidibus, 356 clock, 359
	m_adjust_load_offset, 352	~mastermidibus, 356 clock, 359 continue_from, 360
		clock, 359
	m_adjust_load_offset, 352 m_adjust_ss, 352	clock, 359 continue_from, 360
	m_adjust_load_offset, 352 m_adjust_ss, 352 m_button_learn, 351	clock, 359 continue_from, 360 dump_midi_input, 361
	m_adjust_load_offset, 352 m_adjust_ss, 352 m_button_learn, 351 m_button_perfedit, 352	clock, 359 continue_from, 360 dump_midi_input, 361 filter_by_channel, 358 flush, 359
	m_adjust_load_offset, 352 m_adjust_ss, 352 m_button_learn, 351 m_button_perfedit, 352 m_button_play, 351	clock, 359 continue_from, 360 dump_midi_input, 361 filter_by_channel, 358
	m_adjust_load_offset, 352 m_adjust_ss, 352 m_button_learn, 351 m_button_perfedit, 352 m_button_play, 351 m_button_stop, 351	clock, 359 continue_from, 360 dump_midi_input, 361 filter_by_channel, 358 flush, 359 get_alsa_seq, 357
	m_adjust_load_offset, 352 m_adjust_ss, 352 m_button_learn, 351 m_button_perfedit, 352 m_button_play, 351 m_button_stop, 351 m_call_seq_edit, 353	clock, 359 continue_from, 360 dump_midi_input, 361 filter_by_channel, 358 flush, 359 get_alsa_seq, 357 get_beats_per_minute, 358
	m_adjust_load_offset, 352 m_adjust_ss, 352 m_button_learn, 351 m_button_perfedit, 352 m_button_play, 351 m_button_stop, 351 m_call_seq_edit, 353 m_call_seq_eventedit, 353	clock, 359 continue_from, 360 dump_midi_input, 361 filter_by_channel, 358 flush, 359 get_alsa_seq, 357 get_beats_per_minute, 358 get_clock, 363
	m_adjust_load_offset, 352 m_adjust_ss, 352 m_button_learn, 351 m_button_perfedit, 352 m_button_play, 351 m_button_stop, 351 m_call_seq_edit, 353 m_call_seq_eventedit, 353 m_entry_notes, 352	clock, 359 continue_from, 360 dump_midi_input, 361 filter_by_channel, 358 flush, 359 get_alsa_seq, 357 get_beats_per_minute, 358 get_clock, 363 get_input, 364
	m_adjust_load_offset, 352 m_adjust_ss, 352 m_button_learn, 351 m_button_perfedit, 352 m_button_play, 351 m_button_stop, 351 m_call_seq_edit, 353 m_call_seq_eventedit, 353 m_entry_notes, 352 m_image_play, 351	clock, 359 continue_from, 360 dump_midi_input, 361 filter_by_channel, 358 flush, 359 get_alsa_seq, 357 get_beats_per_minute, 358 get_clock, 363 get_input, 364 get_midi_event, 360
	m_adjust_load_offset, 352 m_adjust_ss, 352 m_button_learn, 351 m_button_perfedit, 352 m_button_play, 351 m_button_stop, 351 m_call_seq_edit, 353 m_call_seq_eventedit, 353 m_entry_notes, 352 m_image_play, 351 m_is_running, 353	clock, 359 continue_from, 360 dump_midi_input, 361 filter_by_channel, 358 flush, 359 get_alsa_seq, 357 get_beats_per_minute, 358 get_clock, 363 get_input, 364 get_midi_event, 360 get_midi_in_bus_name, 358
	m_adjust_load_offset, 352 m_adjust_ss, 352 m_button_learn, 351 m_button_perfedit, 352 m_button_play, 351 m_button_stop, 351 m_call_seq_edit, 353 m_call_seq_eventedit, 353 m_entry_notes, 352 m_image_play, 351 m_is_running, 353 m_main_cursor, 351	clock, 359 continue_from, 360 dump_midi_input, 361 filter_by_channel, 358 flush, 359 get_alsa_seq, 357 get_beats_per_minute, 358 get_clock, 363 get_input, 364 get_midi_event, 360 get_midi_in_bus_name, 358 get_midi_out_bus_name, 358
	m_adjust_load_offset, 352 m_adjust_ss, 352 m_button_learn, 351 m_button_perfedit, 352 m_button_play, 351 m_button_stop, 351 m_call_seq_edit, 353 m_call_seq_eventedit, 353 m_entry_notes, 352 m_image_play, 351 m_is_running, 353 m_main_cursor, 351 m_main_time, 351	clock, 359 continue_from, 360 dump_midi_input, 361 filter_by_channel, 358 flush, 359 get_alsa_seq, 357 get_beats_per_minute, 358 get_clock, 363 get_input, 364 get_midi_event, 360 get_midi_in_bus_name, 358 get_midi_out_bus_name, 358 get_num_in_buses, 357
	m_adjust_load_offset, 352 m_adjust_ss, 352 m_button_learn, 351 m_button_perfedit, 352 m_button_play, 351 m_button_stop, 351 m_call_seq_edit, 353 m_call_seq_eventedit, 353 m_entry_notes, 352 m_image_play, 351 m_is_running, 353 m_main_cursor, 351 m_main_time, 351 m_main_wid, 350	clock, 359 continue_from, 360 dump_midi_input, 361 filter_by_channel, 358 flush, 359 get_alsa_seq, 357 get_beats_per_minute, 358 get_clock, 363 get_input, 364 get_midi_event, 360 get_midi_in_bus_name, 358 get_midi_out_bus_name, 358 get_num_in_buses, 357 get_num_out_buses, 357
	m_adjust_load_offset, 352 m_adjust_ss, 352 m_button_learn, 351 m_button_perfedit, 352 m_button_play, 351 m_button_stop, 351 m_call_seq_edit, 353 m_call_seq_eventedit, 353 m_entry_notes, 352 m_image_play, 351 m_is_running, 353 m_main_cursor, 351 m_main_time, 351 m_main_time, 350 m_menu_edit, 350	clock, 359 continue_from, 360 dump_midi_input, 361 filter_by_channel, 358 flush, 359 get_alsa_seq, 357 get_beats_per_minute, 358 get_clock, 363 get_input, 364 get_midi_event, 360 get_midi_in_bus_name, 358 get_midi_out_bus_name, 358 get_num_in_buses, 357 get_num_out_buses, 357 get_ppqn, 358
	m_adjust_load_offset, 352 m_adjust_ss, 352 m_button_learn, 351 m_button_perfedit, 352 m_button_play, 351 m_button_stop, 351 m_call_seq_edit, 353 m_call_seq_eventedit, 353 m_entry_notes, 352 m_image_play, 351 m_is_running, 353 m_main_cursor, 351 m_main_time, 351 m_main_time, 351 m_main_wid, 350 m_menu_edit, 350 m_menu_file, 350	clock, 359 continue_from, 360 dump_midi_input, 361 filter_by_channel, 358 flush, 359 get_alsa_seq, 357 get_beats_per_minute, 358 get_clock, 363 get_input, 364 get_midi_event, 360 get_midi_in_bus_name, 358 get_midi_out_bus_name, 358 get_num_in_buses, 357 get_num_out_buses, 357 get_ppqn, 358 get_sequence, 361
	m_adjust_load_offset, 352 m_adjust_ss, 352 m_button_learn, 351 m_button_perfedit, 352 m_button_play, 351 m_button_stop, 351 m_call_seq_edit, 353 m_call_seq_eventedit, 353 m_entry_notes, 352 m_image_play, 351 m_is_running, 353 m_main_cursor, 351 m_main_time, 351 m_main_time, 351 m_menu_edit, 350 m_menu_file, 350 m_menu_help, 350	clock, 359 continue_from, 360 dump_midi_input, 361 filter_by_channel, 358 flush, 359 get_alsa_seq, 357 get_beats_per_minute, 358 get_clock, 363 get_input, 364 get_midi_event, 360 get_midi_in_bus_name, 358 get_midi_out_bus_name, 358 get_num_in_buses, 357 get_num_out_buses, 357 get_ppqn, 358 get_sequence, 361 init, 357
	m_adjust_load_offset, 352 m_adjust_ss, 352 m_button_learn, 351 m_button_perfedit, 352 m_button_play, 351 m_button_stop, 351 m_call_seq_edit, 353 m_call_seq_eventedit, 353 m_entry_notes, 352 m_image_play, 351 m_is_running, 353 m_main_cursor, 351 m_main_time, 351 m_main_time, 351 m_main_wid, 350 m_menu_edit, 350 m_menu_file, 350 m_menu_file, 350 m_menu_help, 350 m_menu_view, 350 m_menu_view, 350 m_menu_view, 350 m_menu_view, 350 m_menu_view, 350 m_menubar, 350	clock, 359 continue_from, 360 dump_midi_input, 361 filter_by_channel, 358 flush, 359 get_alsa_seq, 357 get_beats_per_minute, 358 get_clock, 363 get_input, 364 get_midi_event, 360 get_midi_in_bus_name, 358 get_midi_out_bus_name, 358 get_num_in_buses, 357 get_num_out_buses, 357 get_ppqn, 358 get_sequence, 361 init, 357 init_clock, 360 is_dumping, 361 is_more_input, 360
	m_adjust_load_offset, 352 m_adjust_ss, 352 m_button_learn, 351 m_button_perfedit, 352 m_button_play, 351 m_button_stop, 351 m_call_seq_edit, 353 m_call_seq_eventedit, 353 m_entry_notes, 352 m_image_play, 351 m_is_running, 353 m_main_cursor, 351 m_main_time, 351 m_main_wid, 350 m_menu_edit, 350 m_menu_edit, 350 m_menu_file, 350 m_menu_help, 350 m_menu_mode, 353 m_menu_view, 350	clock, 359 continue_from, 360 dump_midi_input, 361 filter_by_channel, 358 flush, 359 get_alsa_seq, 357 get_beats_per_minute, 358 get_clock, 363 get_input, 364 get_midi_event, 360 get_midi_in_bus_name, 358 get_midi_out_bus_name, 358 get_num_in_buses, 357 get_num_out_buses, 357 get_ppqn, 358 get_sequence, 361 init, 357 init_clock, 360 is_dumping, 361
	m_adjust_load_offset, 352 m_adjust_ss, 352 m_button_learn, 351 m_button_perfedit, 352 m_button_play, 351 m_button_stop, 351 m_button_stop, 351 m_call_seq_edit, 353 m_call_seq_eventedit, 353 m_entry_notes, 352 m_image_play, 351 m_is_running, 353 m_main_cursor, 351 m_main_time, 351 m_main_time, 351 m_main_wid, 350 m_menu_edit, 350 m_menu_edit, 350 m_menu_help, 350 m_menu_help, 350 m_menu_wiew, 350 m_menu_view, 350 m_menu_view, 350 m_menu_view, 350 m_options, 351 m_perf_edit, 351	clock, 359 continue_from, 360 dump_midi_input, 361 filter_by_channel, 358 flush, 359 get_alsa_seq, 357 get_beats_per_minute, 358 get_clock, 363 get_input, 364 get_midi_event, 360 get_midi_in_bus_name, 358 get_midi_out_bus_name, 358 get_num_in_buses, 357 get_num_out_buses, 357 get_ppqn, 358 get_sequence, 361 init, 357 init_clock, 360 is_dumping, 361 is_more_input, 360 m_alsa_seq, 364 m_beats_per_minute, 365
	m_adjust_load_offset, 352 m_adjust_ss, 352 m_button_learn, 351 m_button_perfedit, 352 m_button_play, 351 m_button_stop, 351 m_call_seq_edit, 353 m_call_seq_eventedit, 353 m_entry_notes, 352 m_image_play, 351 m_is_running, 353 m_main_cursor, 351 m_main_time, 351 m_main_time, 351 m_main_wid, 350 m_menu_edit, 350 m_menu_file, 350 m_menu_help, 350 m_menu_mode, 353 m_menu_view, 350 m_menu_view, 350 m_menubar, 350 m_options, 351	clock, 359 continue_from, 360 dump_midi_input, 361 filter_by_channel, 358 flush, 359 get_alsa_seq, 357 get_beats_per_minute, 358 get_clock, 363 get_input, 364 get_midi_event, 360 get_midi_in_bus_name, 358 get_midi_out_bus_name, 358 get_num_in_buses, 357 get_num_out_buses, 357 get_ppqn, 358 get_sequence, 361 init, 357 init_clock, 360 is_dumping, 361 is_more_input, 360 m_alsa_seq, 364
	m_adjust_load_offset, 352 m_adjust_ss, 352 m_button_learn, 351 m_button_perfedit, 352 m_button_play, 351 m_button_stop, 351 m_button_stop, 351 m_call_seq_edit, 353 m_call_seq_eventedit, 353 m_entry_notes, 352 m_image_play, 351 m_is_running, 353 m_main_cursor, 351 m_main_time, 351 m_main_time, 351 m_menu_edit, 350 m_menu_file, 350 m_menu_help, 350 m_menu_node, 353 m_menu_view, 350 m_menu_view, 350 m_options, 351 m_perf_edit, 351 m_perf_edit_2, 351 m_ppqn, 350	clock, 359 continue_from, 360 dump_midi_input, 361 filter_by_channel, 358 flush, 359 get_alsa_seq, 357 get_beats_per_minute, 358 get_clock, 363 get_input, 364 get_midi_event, 360 get_midi_in_bus_name, 358 get_midi_out_bus_name, 358 get_num_in_buses, 357 get_num_out_buses, 357 get_ppqn, 358 get_sequence, 361 init, 357 init_clock, 360 is_dumping, 361 is_more_input, 360 m_alsa_seq, 364 m_beats_per_minute, 365
	m_adjust_load_offset, 352 m_adjust_ss, 352 m_button_learn, 351 m_button_perfedit, 352 m_button_play, 351 m_button_stop, 351 m_button_stop, 351 m_call_seq_edit, 353 m_call_seq_eventedit, 353 m_entry_notes, 352 m_image_play, 351 m_is_running, 353 m_main_cursor, 351 m_main_time, 351 m_main_wid, 350 m_menu_edit, 350 m_menu_file, 350 m_menu_file, 350 m_menu_help, 350 m_menu_view, 350 m_menu_view, 350 m_menu_view, 350 m_options, 351 m_perf_edit_2, 351 m_ppqn, 350 m_sigpipe, 350	clock, 359 continue_from, 360 dump_midi_input, 361 filter_by_channel, 358 flush, 359 get_alsa_seq, 357 get_beats_per_minute, 358 get_clock, 363 get_input, 364 get_midi_event, 360 get_midi_in_bus_name, 358 get_midi_out_bus_name, 358 get_num_in_buses, 357 get_num_out_buses, 357 get_ppqn, 358 get_sequence, 361 init, 357 init_clock, 360 is_dumping, 361 is_more_input, 360 m_alsa_seq, 364 m_beats_per_minute, 365 m_buses_in, 364 m_buses_in_active, 365
	m_adjust_load_offset, 352 m_adjust_ss, 352 m_button_learn, 351 m_button_perfedit, 352 m_button_play, 351 m_button_stop, 351 m_button_stop, 351 m_call_seq_edit, 353 m_call_seq_eventedit, 353 m_entry_notes, 352 m_image_play, 351 m_is_running, 353 m_main_cursor, 351 m_main_time, 351 m_main_wid, 350 m_menu_edit, 350 m_menu_file, 350 m_menu_file, 350 m_menu_help, 350 m_menu_view, 350 m_menu_view, 350 m_menu_view, 350 m_options, 351 m_perf_edit, 351 m_perf_edit, 2, 351 m_ppqn, 350 m_sigpipe, 350 m_spinbutton_bpm, 352	clock, 359 continue_from, 360 dump_midi_input, 361 filter_by_channel, 358 flush, 359 get_alsa_seq, 357 get_beats_per_minute, 358 get_clock, 363 get_input, 364 get_midi_event, 360 get_midi_in_bus_name, 358 get_midi_out_bus_name, 358 get_num_in_buses, 357 get_num_out_buses, 357 get_ppqn, 358 get_sequence, 361 init, 357 init_clock, 360 is_dumping, 361 is_more_input, 360 m_alsa_seq, 364 m_beats_per_minute, 365 m_buses_in, 364 m_buses_in_active, 365 m_buses_in_init, 365
	m_adjust_load_offset, 352 m_adjust_ss, 352 m_button_learn, 351 m_button_perfedit, 352 m_button_play, 351 m_button_stop, 351 m_button_stop, 351 m_call_seq_edit, 353 m_call_seq_eventedit, 353 m_entry_notes, 352 m_image_play, 351 m_is_running, 353 m_main_cursor, 351 m_main_time, 351 m_main_wid, 350 m_menu_edit, 350 m_menu_file, 350 m_menu_file, 350 m_menu_help, 350 m_menu_view, 350 m_menu_view, 350 m_menu_view, 350 m_options, 351 m_perf_edit_2, 351 m_ppqn, 350 m_sigpipe, 350	clock, 359 continue_from, 360 dump_midi_input, 361 filter_by_channel, 358 flush, 359 get_alsa_seq, 357 get_beats_per_minute, 358 get_clock, 363 get_input, 364 get_midi_event, 360 get_midi_in_bus_name, 358 get_midi_out_bus_name, 358 get_num_in_buses, 357 get_num_out_buses, 357 get_ppqn, 358 get_sequence, 361 init, 357 init_clock, 360 is_dumping, 361 is_more_input, 360 m_alsa_seq, 364 m_beats_per_minute, 365 m_buses_in, 364 m_buses_in_active, 365

m_buses_out_active, 365 m buses out init, 365 m_dumping_input, 366 m_filter_by_channel, 366 m_nilticlock, 365 m_init_input, 366 m_init_input, 365 m_mint_input, 365 m_mint_input, 365 m_mint_input, 365 m_mint_buses, 364 m_mumbuses, 364 m_num_out_buses, 364 m_num_out_buses, 364 m_num_poll_descriptors, 366 m_popn, 365 m_out_a, 366 m_popn, 365 m_geue, 366 m_popn, 365 m_wector_sequence, 366 m_vector_sequence, 366 m_vector_sequence, 366 m_seq, 366 m_vector_sequence, 366 m_set_a, 362 polf_for_midi, 360 port_exit, 362 polf_start, 362 port_start, 362 port_start, 362 port_start, 362 port_start, 363 set_input, 363 set_input, 363 set_sequence_input, 361 start, 359 sot_sequence_input, 361 start, 359 sitp, 359 sitp, 359 sitp, 359 sitp, 359 sitp, 359 sitp, 357 set_sequence, 374 add_short, 372 add_long, 371 add_short, 372 add_long, 371 add_short, 372 add_long, 371 add_short, 372 afl_lseq_number, 372 fill_seq_number, 372 fill_seq_number, 372 fill_seq_number, 373 get, 370 m_position_for_get, 374 m_sequence, 374 mid_container, 369 midfile, 374 position_get, 374 position_reset, 371 position_nersemt, 371		
m_dumping_input, 366 m_filter_by_channel, 366 m_filter_by_channel, 366 m_init_loput, 365 m_init_input, 365 m_max_busses, 364 m_mum_in_busses, 364 m_num_out_busses, 364 m_num_out_busses, 364 m_num_out_busses, 364 m_num_out_busses, 364 m_num_poll_descriptors, 366 m_poll_descriptors, 366 midi_contale, 369 all_seq_tim_descriptors, 366 m_poll_descriptors, 366 m_poll_descriptors, 376 m_loal_seq_tim_descriptors, 371 m_descriptors, 373 fill_seq_nome, 372 fill_time_sig_and_tempo, 373 get, 370 m_position_for_get, 374 m_sequence, 374 m_sequence, 374 m_sequence, 374 m_sequence, 374 midi_container, 369 midifile, 374 position_grapt, 374 m_sequence, 374 position_increment, 371 position_increment, 371 position_increment, 371 position_reset, 371 position_increment, 371 position_reset, 371 position_increment, 371 position_reset, 371 position_proll_seq_tim_get, 374 m_beats_per_minute, 391 m_beats_per_minute, 391 m_beats_per_minute, 391 m_beats_per_minute, 391 m_pan, 391	m_buses_out_active, 365	data, 376
m_filler_by_channel, 366 m_init_clock, 365 m_mint_cloput, 365 m_max_busses, 364 m_num_busses, 364 m_num_in_buses, 364 m_num_out_buses, 364 m_num_poll_descriptors, 366 m_poll_descriptors, 366 m_seq, 366 m_seq, 366 m_seq, 366 m_set_ord, 360 m_set_ord, 360 m_set_ord, 360 port_exit, 362 poll_for_midi, 360 port_exit, 362 poll_for_midi, 360 port_exit, 362 port_start, 362 port_start, 362 port_start, 362 port_start, 362 port_start, 363 set_input, 363 set_input, 363 set_input, 363 set_input, 363 set_input, 363 set_input, 363 set_ord, 373 set_sequence_input, 361 start, 359 stop, 359 stop, 359 stop, 359 stop, 359 stop, 359 stop, 370 m_dest_ord, 372 add_long, 371 add_short, 372 add_variable, 371 clear, 371 done, 370 fill_seq_name, 372 fill_time_sig_and_tempo, 373 get, 370 m_position_for_get, 374 m_sequence, 374 m_isequence, 374 m_isequence, 374 m_isequence, 374 m_isequence, 374 m_idi_container, 369 midifflie, 374 position_increment, 371 pos	:	_ •
m_init_clock, 365 m_init_input, 365 m_max_busses, 364 m_mutex, 366 m_num_in_busses, 364 m_num_out_busses, 364 m_num_poll_descriptors, 366 m_poll_descriptors, 366 m_lescriptors, 366 m_outlescriptors, 366 m_lescriptors, 376 milescriptors, 378 milescriptors, 378 milescriptors, 378 milescriptors, 378 m_lescriptors, 37		
m_init_input, 365 m_max_busses, 364 m_mutex, 366 m_num_in_buses, 364 m_num_in_buses, 364 m_num_out_buses, 364 m_num_out_buses, 364 m_num_out_buses, 364 m_num_joll_descriptors, 366 m_poll_descriptors, 366 m_local_descriptors, 376 m_local_descriptors, 366 m_local_descriptors, 377 m_local_descriptors, 366 m_local_descriptors, 378 m_local_descriptor, 378 m_local_descriptor, 378 m_l		<u> </u>
m_max_buses, 364 m_mutex, 366 m_muter, 366 m_muter, 366 m_num_in_buses, 364 m_num_out_buses, 364 m_num_out_buses, 364 m_num_out_buses, 364 m_num_out_buses, 364 m_num_out_buses, 366 m_num_oil_descriptors, 366 m_popil_descriptors, 366 m_popil_descriptors, 366 m_popil_descriptors, 366 m_popil_descriptors, 366 m_popil_descriptors, 366 m_yout_oil_descriptors, 369 m_yout_oil_descriptors, 367 m_descriptors, 366 m_yout_oil_descriptors, 366 m_yout_oil_des	m_init_clock, 365	m_data, 378
m_mutex, 366 m_num_in_buses, 364 m_num_jot_buses, 364 m_num_jot_buses, 364 m_num_pot_lescriptors, 366 m_poli_descriptors, 378 m_sel_dels, 371 done, 370 m_position_folet, 374 m_sequence, 374 m_sequence, 374 m_sequence, 374 m_sequence, 374 m_sequence, 375 sill_seq_name, 372 fill_time_sig_and_tempo, 373 get, 370 m_position_folet, 371 position_foleter, 369 midifile, 374 position_incerement, 371 position_incerement, 373 m_beats_per_minute, 390 m_beats_per_minute, 391 m_beats_per_minute, 391 m_beats_per_minute, 391 m_beats_per_minute, 391	m_init_input, 365	m_inverse_active, 377
m_num_out_buses, 364 m_num_out_buses, 364 m_num_out_buses, 364 m_num_out_buses, 364 m_num_out_buses, 366 m_poll_descriptors, 366 m_poll_descriptors, 366 m_poll_descriptors, 366 m_poll_descriptors, 366 m_poll_descriptors, 366 m_poll_descriptors, 366 m_yeucl_ 365 m_queue, 365 m_yeucl_ 366 m_vector_sequence, 366 m_vector_sequence, 366 m_set_midi_list, 378 m_seq, 362 poll_for_midi, 360 port_exit, 362 port_start, 362 port_start, 362 port_start, 362 port_start, 362 port_start, 362 port_start, 363 set_input, 363 set_input, 363 set_input, 363 set_pap, 357 set_sequence_input, 361 start, 359 stop, 359 stop, 359 sysex, 362 seq64::midi_container, 367 m_measures, 384 m_adi_short, 372 add_short, 372 add_short, 372 add_long, 371 add_short, 372 add_short, 372 add_long, 371 clear, 371 clear, 371 clear, 371 clear, 371 clear, 371 done, 370 fill_seq_name, 372 fill_time_sig_and_tempo, 373 get, 370 m_position_for_get, 374 m_sequence, 384 m_sml0_channels_count, 388 m_sml0_channels_count, 388 m_sml0_nain_sequence, 386 m_sml0_main_sequence, 388 m_sml0_nain_sequence, 388 m_sml0_nain_sequence, 388 m_sml0_nain_sequence, 388 m_sml0_channels_count, 388 m_sml0_nain_sequence, 388 m_sml0_seq_name, 372 m_nosition_for_get, 374 m_sequence, 374 m_sequence, 374 m_sequence, 374 m_sequence, 375 position_increment, 371 position_increment, 371 position_increment, 371 position_increment, 371 position_increment, 371 position_reset, 371 position_reset, 371 position_reset, 371 position_fortol, 374 m_beats_per_measure, 390 beats_per_minute, 391 m_beats_per_minute, 391 m_beats_per_measure, 391 m_beats_per_minute, 391 m_beats_per_minute, 391 m_beats_per_minute, 391	m_max_busses, 364	m_max_value, 378
m_num_out_buses, 364 m_num_poll_descriptors, 366 m_poll_descriptors, 366 m_poll_descriptors, 366 m_poll_descriptors, 366 m_poll_descriptors, 366 m_poll_descriptors, 365 m_queue, 365 m_seq, 366 m_seq, 366 m_seq, 366 m_vector_sequence, 366 m_stermidibus, 356 play, 362 poll_for_midi, 360 port_exit, 362 poll_for_midi, 360 port_exit, 362 port_start, 362 port_start, 362 port_start, 362 port_start, 363 set_input, 361 start, 359 stop, 369 stop, 371 seq64:midi_container, 369 stop, 371 stop, 371 stop, 381 stop, 382 stop, 383 stop, 384	m_mutex, 366	m_min_value, 378
m_num_poll_descriptors, 366 m_poll_descriptors, 376 m_poll_descriptors, 366 m_poll_descriptors, 376 m_poll_descriptors, 366 m_poll_descriptors, 376 m_poll_descriptors, 376 mid_contailer, 367 m_sequence, 381 m_descriptors, 382 seq64:midi_lentailer, 367 m_easures, 383 midi_measures, 384 m_divisions, 384 m_measures, 384 m_divisions, 384 m_measures, 384 m_divisions, 384 m_measures, 382 seq64:midi_container, 369 add_event, 372 add_long, 371 add_short, 372 add_long, 371 add_short, 372 add_variable, 371 clear, 371 done, 370 fill_seq_name, 372 fill_ten_sig_and_tempo, 373 get, 370 m_position_for_get, 374 m_sequence, 375 m_beat_width, 391 m_beat_sper_measure, 390 beats_per_measure, 391 m_beat_per_minute, 391 m_beat_per_minute, 391 m_beat_per_minute, 391 m_popq, 391	m_num_in_buses, 364	m_status, 377
m_poll_descriptors, 366 m_popq, 365 m_popq, 365 m_queue, 365 m_seq, 366 m_vector_sequence, 366 m_stermidibus, 356 play, 362 poll_for_midi, 360 port_exit, 362 port_start, 362 port_start, 362 port_start, 362 port_start, 362 port_start, 363 set_loput, 363 set_input, 363 set_input, 363 set_popq, 357 set_sequence_input, 361 start, 359 stop, 367 ¬midi_container, 367 ¬measures, 382 seq64::midi_splitter, 381 seq64::midi_sting, 381 size, 381 seq64::midi_sting, 381 size, 381 seq64::midi_liet, 380 clear, 381 done, 381 position, 539 stop, 381 seq64::midi_liet, 380 clear, 381 mid_stop, 381 seq64::midi_stop, 380 put, 381 size, 381 seq64::midi_liet, 380 clear, 381 done, 381 position, 383 size, 381 seq64::midi_liet, 380 clear, 381 mid_stop, 381 seq64::midi_liet, 380 clear, 381 done, 381 position, sa81 mid_ist, 380 put, 381 size, 381 seq64::midi_stonialiet, 380 size, 381 seq64::midi_seq. sa8 m_smf0_chanels_count, 388 m_smf0_chanels_count, 388 m_smf0_chanels_count, 388 m_smf0_chanels_count, 388 m_smf0_chanels_count, 388 m_smf0_chanels_count, 388 m	m_num_out_buses, 364	match, 377
m_ppqn, 365 m_queue, 365 m_queue, 366 m_seq, 366 m_vector_sequence, 366 m_vector_sequence, 366 m_vector_sequence, 366 m_stermidibus, 356 play, 362 pol_for_midi, 360 port_exit, 362 port_start, 362 port_start, 362 port_start, 362 port_start, 363 set_input, 363 set_input, 363 set_input, 363 set_ppqn, 357 set_sequence_input, 361 start, 359 stop, 359 stop, 359 stop, 359 stop, 359 stop, 359 add_event, 372 add_long, 371 add_short, 372 add_long, 371 add_short, 372 add_long, 371 clear, 371 done, 370 m_position_for_get, 374 midi_container, 369 midifile, 374 position_increment, 371 position_reset, 371 position_increment, 372 seq64:midi_seq_rumber, 388 m_smf0_channels_ 388 m_smf0_seq_number, 389 m_smf0_seq_number, 388 m_smf0_seq_number, 388 m_smf0_seq_nu	m_num_poll_descriptors, 366	max_value, 376
m_queue, 365 m_seq, 366 m_seq, 366 m_vector_sequence, 366 m_vector_sequence, 366 mastermidibus, 356 play, 362 poll_for_midi, 360 port_exit, 362 port_start, 362 port_start, 362 port_start, 362 port_start, 362 port_start, 363 set_input, 363 set_input, 363 set_input, 363 set_popn, 357 set_sequence_input, 361 start, 359 stop, 359 sysex, 362 seq64::midi_container, 367 ~midi_container, 367 ~midi_container, 369 add_event, 372 add_long, 371 add_short, 372 add_variable, 371 clear, 371 done, 370 fill_s69 midifle, 374 position_rerement, 371 position_increment, 371 position_increment, 371 position_increment, 371 position_increment, 371 seq64::midi_lst, 380 clear, 381 seq64::midi_measures, 381 size, 381 m_char_list, 381 midi_ist, 380 clear, 381 m_char_list, 381 midi_ist, 380 put, 381 size, 382 beats, 383 divisions, 383 m_beats, 384 m_measures, 382 seq64::midi_container, 382 m_measures, 384 measures, 383 midi_measures, 384 measures, 383 midi_measures, 382 seq64::midi_splitter, 384 count, 387 count, 387 increment, 386 initialize, 386 log_main_sequence, 386 m_ppqn, 388 m_smf0_channels_count, 388 m_smf0_channels_count, 388 m_smf0_channels_count, 388 m_smf0_channels_count, 388 m_smf0_channels_count, 388 m_smf0_channels_count, 388 m_smf0_seq_number, 388 m_smf0_channels_sequence, 388 m_smf0_seq_number, 389 midi_splitter, 385 popn, 387 seq_64::midi_timing, 388 beat_width, 390 beats_per_minute, 390 m_beat_sper_minute, 391 m_beats_per_minute, 391 m_beats_per_minute, 391 m_peqn, 391	m_poll_descriptors, 366	midi_control, 376
m_seq, 366 m_vector_sequence, 366 m_vector_sequence, 366 m_vector_sequence, 366 m_astermidibus, 356 play, 362 poll_for_midi, 360 port_exit, 362 poll_for_midi, 360 port_exit, 362 port_start, 362 print, 359 set_beats_per_minute, 357 set_clock, 363 set_input, 363 set_input, 363 set_pap, 357 set_sequence_input, 361 start, 359 stop, 359 stop, 359 stop, 359 stop, 359 stop, 359 add_event, 372 add_long, 371 add_short, 372 add_short, 372 add_variable, 371 clear, 371 clear, 371 done, 370 fill_seq_number, 372 fill_seq_number, 372 fill_seq_number, 372 fill_seq_number, 372 fill_seq_number, 372 fill_seq_number, 372 m_position_increment, 371 position_increment, 371 position_reset, 371 positio	m_ppqn, 365	min_value, 376
m_vector_sequence, 366 mastermidibus, 356 play, 362 poll_for_midi, 360 port_exit, 362 poll_for_midi, 360 port_exit, 362 port_start, 362 port_start, 362 port_start, 362 port_start, 362 port_start, 362 port_start, 363 set_beats_per_minute, 357 set_clock, 363 set_input, 363 set_ppqn, 357 set_sequence_input, 361 start, 359 stop, 359 sysex, 362 seq64::midi_container, 367 ~midi_container, 367 ~midi_container, 369 add_event, 372 add_long, 371 add_short, 372 add_variable, 371 clear, 371 done, 370 fill_aseq_number, 372 fill_time_sig_and_tempo, 373 get, 370 m_position_for_get, 374 m_sequence, 374 m_sequence, 374 m_sequence, 374 m_sequence, 377 position_increment, 371 position_reset, 371 position_res	m_queue, 365	set, 376, 377
mastermidibus, 356 play, 362 poll, or, midi, 360 port_exit, 362 port_exit, 362 port_start, 363 set_port_start, 363 set_load, 363 set_input, 363 set_input, 363 set_port, 357 set_sequence_input, 361 start, 359 stop, 359 stop, 359 stop, 359 stop, 359 stop, 359 stop, 359 add_event, 372 add_long, 371 add_short, 372 add_long, 371 add_short, 372 add_long, 371 add_short, 372 add_long, 371 clear, 371 done, 370 fill, 369 fill_meta_track_end, 373 fill_perprietary, 373 fill_perprietary, 373 fill_seq_name, 372 fill_seq_name, 372 fill_time_sig_and_tempo, 373 get, 370 m_position_for_get, 374 m_sequence, 374 mid_container, 369 midffile, 374 position_increment, 371 position_reset, 371 put, 370 size, 370 song_fill_seq_event, 373 song_fill_seq_trigger, 374 m_beats_per_measure, 390 m_beats_per_measure, 391 m_beats_per_minute, 391	m_seq, 366	status, 376
play, 362 poll_for_midi, 360 port_exit, 362 poll_for_midi, 360 port_exit, 362 port_start, 362 port_start, 362 print, 359 set_beats_per_minute, 357 set_clock, 363 set_input, 363 set_input, 363 set_ppqn, 357 set_sequence_input, 361 start, 359 stop, 359 sysex, 362 seq64::midi_container, 367 ~midi_container, 367 ~midi_container, 369 add_event, 372 add_long, 371 add_short, 372 add_long, 371 add_short, 372 add_variable, 371 clear, 371 done, 370 fill_seq_name, 372 fill_time_sig_and_tempo, 373 get, 370 m_position_increment, 371 position_increment, 371 position_increment, 371 position_increment, 371 position_increment, 371 position_reset, 371 position_increment, 371 position_increment, 371 position_increment, 371 position_increment, 371 position_increment, 371 position_increment, 371 position_reset, 371 put, 370 size, 370 song_fill_seq_trigger, 374 m_beats_per_minute, 390 m_beats_per_minute, 391 m_pagn, 391	m_vector_sequence, 366	seq64::midi_list, 378
poll_for_midi, 360 port_exit, 362 port_start, 362 port_start, 362 port_start, 362 port_start, 362 print, 359 set_beats_per_minute, 357 set_clock, 363 set_ppqn, 357 set_sequence_input, 361 start, 359 stop, 359 sysex, 362 seq64::midi_container, 367	mastermidibus, 356	\sim midi_list, 380
port_exit, 362 port_start, 363 set_beats_per_minute, 357 set_clock, 363 set_input, 363 set_ppqn, 357 set_sequence_input, 361 start, 359 stop, 359 stop, 359 stop, 359 stop, 359 stop, 359 stop, 369 sysex, 362 seq64::midi_container, 367	play, 362	CharList, 380
port_start, 362 print, 359 set_beats_per_minute, 357 set_clock, 363 set_input, 363 set_ppqn, 357 set_sequence_input, 361 start, 359 stop, 359 sysex, 362 seq64::midi_container, 367 ~midi_container, 369 add_event, 372 add_long, 371 add_short, 372 add_variable, 371 clear, 371 done, 370 fill_meta_track_end, 373 fill_proprietary, 373 fill_seq_number, 372 fill_time_sig_and_tempo, 373 get, 370 m_position_for_get, 374 mposition_for_eset, 371 position_increment, 371 position_increment, 371 position_increment, 371 position_increment, 371 position_increment, 371 position_reset, 371 put, 370 size, 370 song_fill_seq_event, 373 song_fill_seq_trigger, 374 seq64::midi_control, 374 m_beats_per_measure, 391 m_popqn, 391 get, 381 m_char_list, 381 m_idi_list, 380 put, 381 size, 381 size, 381 seq64::mid_iiliti, 380 put, 381 size, 383 divisions, 383 m_beats_per_minute, 391 m_post, 384 m_divisions, 383 m_measures, 382 seq64::midi_measures, 382 seq64::midi_enthesion, 388 m_smf0_channels_count, 388 m_smf0_channels_count, 388 m_smf0_channels_count, 388 m_smf0_channels_count, 388 m_smf0_seq_number, 388 m_smf0_seq_number, 388 m_smf0_seq_number, 388 m_smf0	poll_for_midi, 360	clear, <mark>381</mark>
print, 359 set_beats_per_minute, 357 set_clock, 363 set_input, 363 set_input, 363 set_ppqn, 357 set_sequence_input, 361 start, 359 stop, 359 stop, 359 sysex, 362 seq64::midi_container, 367 ~midi_container, 367 ~midi_container, 369 add_event, 372 add_long, 371 add_short, 372 add_variable, 371 clear, 371 done, 370 fill_seq_name, 372 fill_time_sig_and_tempo, 373 get, 370 m_position_increment, 371 position, 371 position_reset, 371 position_reset, 371 position_reset, 371 position_reset, 371 position_reset, 371 seq64::midi_seliter, 384 midi_list, 388 midi_measures, 382 seq64::midi_splitter, 384 measures, 383 midi_measures, 382 seq64::midi_splitter, 384 measures, 383 midi_measures, 382 seq64::midi_splitter, 384 midi_splitter, 386 count, 387 increment, 386 initialize, 386 log_main_sequence, 386 m_ppqn, 388 m_smf0_channels, 388 m_smf0_channels, 388 m_smf0_channels, 388 m_smf0_equence, 388 m_smf0_seq_number, 388 m_use_default_ppqn, 388 midi_splitter, 385 ppqn, 387 seq64::midi_timing, 388 beat_width, 390 beats_per_minute, 390 m_beat_width, 390 beats_per_minute, 390 m_beat_width, 391 m_beats_per_minute, 391 m_beats_per_minute, 391 m_beats_per_minute, 391 m_ppqn, 391	port_exit, 362	done, 381
set_beats_per_minute, 357 set_clock, 363 set_input, 363 set_input, 363 set_ppqn, 357 set_sequence_input, 361 start, 359 stop, 359 stop, 359 sysex, 362 seq64::midi_container, 367 ~midi_container, 369 add_event, 372 add_long, 371 done, 370 fill_proprietary, 373 fill_seq_name, 372 fill_time_sig_and_tempo, 373 get, 370 m_position_for_get, 374 mposition_increment, 371 position_reset, 371 position_reset, 371 post_per_minute, 373 song_fill_seq_rtigger, 374 seq64::midi_sont midi_list, 380 put, 381 size, 382 beats, 382 beat, indii_measures, 382 beat, indii_measures, 382 seq64::midi_measures, 382 size, 370 song_fill_seq_rigger, 374 seq64::midi_control, 374 increment, 386 initialize, 386 log_main_sequence, 386 m_pxpn, 388 m_smf0_channels, 388 m_smf0_channels, 388 m_smf0_channels, 388 m_smf0_seq_unther, 388 midi_splitter, 385 size, 370 size, 370 size, 370 song_fill_seq_rigger, 374 seq64::midi_control, 374 seq64::midi_measures, 382 seq64::midi_splitter, 385 size, 370 seq64::midi_splitter, 386 sizt_ivition_splitter, 386 sizt_ivition_splitter, 386 sivition_splitter, 386 size, 370 size, 370 size, 370 size, 370	port_start, 362	get, 381
set_clock, 363 set_input, 363 set_input, 363 set_ppqn, 357 set_sequence_input, 361 start, 359 stop, 359 stop, 359 sysex, 362 seq64::midi_container, 367 ~midi_container, 369 add_event, 372 add_long, 371 add_short, 372 add_variable, 371 clear, 371 done, 370 fill_seq_name, 372 fill_time_sig_and_tempo, 373 get, 370 m_position_increment, 371 position_reset, 371 position_reset, 371 put, 370 size, 370 size, 370 size, 370 song_fill_seq_event, 373 song_fill_seq_trigger, 374 seq64::midi_contine, 381 seze(3::midi_measures, 382 seq64::midi_splitter, 384 m_divisions, 384 m_divisions, 384 m_divisions, 384 m_measures, 383 midi_measures, 383 midi_neasures, 383 midi_neasures, 383 midi_neasures, 384 m_emasures, 383 midi_neasures, 384 m_emasures, 383 midi_neasures, 384 m_emasures, 384 m_emasures, 383 midi_neasures, 382 seq64::midi_splitter, 384 count, 387 m_smf0_enanels_count, 388 m_usmf0_enanels_count, 388 m_usm_edefault_ppqn, 388 midi_splitter, 385 ppqn, 387 split, 386 split_channel, 387 seq64::midi_timing, 388 beat_width, 390 beats_per_measure, 390 beats_per_minute, 390 m_beat_width, 391 m_beats_per_minute, 391 m_beats_per_minute, 391 m_beats_per_minute, 391 m_pan, 391	print, 359	m_char_list, 381
set_input, 363 size, 381 set_ppqn, 357 seq64:::midi_measures, 382 set_sequence_input, 361 beats, 383 start, 359 divisions, 383 stop, 359 m_beats, 384 sysex, 362 m_divisions, 384 seq64::midi_container, 367 m_measures, 384 ~midi_container, 369 masaures, 383 add_verent, 372 midi_measures, 382 add_long, 371 seq64::midi_splitter, 384 ~midi_splitter, 384 ~midi_splitter, 386 dolong, 371 count, 387 iclear, 371 increment, 386 done, 370 initialize, 386 fill, 369 log_main_sequence, 386 fill_meta_track_end, 373 m_ppqn, 388 fill_seq_name, 372 m_smf0_channels_count, 388 fill_seq_name, 372 m_smf0_channels_count, 388 fill_time_sig_and_tempo, 373 m_smf0_seq_uence, 388 m_position_for_get, 374 muse_default_ppqn, 388 m_sequence, 374 midi_splitter, 385 ppqn, 387 split, 386 midi-splitter, 389 split, 386 midi-splitt	set_beats_per_minute, 357	midi_list, 380
set_ppqn, 357 seq64::midi_measures, 382 set_sequence_input, 361 beats, 383 start, 359 divisions, 383 stop, 359 m_beats, 384 sysex, 362 m_divisions, 384 seq64::midi_container, 367 m_measures, 384 ~midi_container, 369 measures, 383 add_event, 372 midi_measures, 382 add_long, 371 seq64::midi_splitter, 384 add_short, 372 add_splitter, 386 add_variable, 371 count, 387 clear, 371 increment, 386 done, 370 initialize, 386 fill, 369 log_main_sequence, 386 fill_proprietary, 373 m_smf0_channels, 388 fill_seq_number, 372 m_smf0_channels, 388 fill_seq_number, 372 m_smf0_channels, 20unt, 388 fill_time_sig_and_tempo, 373 m_smf0_main_sequence, 388 m_position_for_get, 374 m_sequence, 388 m_sequence, 374 m_sequence, 374 midi_container, 369 split_channel, 387 seq64::midi_timing, 388 beat_width, 390 beats_per_measure, 390 beats_per_measure, 390 <td>set_clock, 363</td> <td>put, 381</td>	set_clock, 363	put, 381
set_sequence_input, 361 beats, 383 start, 359 divisions, 383 stop, 359 m_beats, 384 syesx, 362 m_divisions, 384 seq64::midi_container, 369 m_aesures, 383 add_event, 372 measures, 383 add_event, 372 measures, 382 add_long, 371 seq64::midi_splitter, 384 add_short, 372 add_splitter, 386 add_variable, 371 count, 387 clear, 371 increment, 386 done, 370 initialize, 386 fill, 369 log_main_sequence, 386 fill_proprietary, 373 m_ppqn, 388 fill_seq_name, 372 m_smf0_channels_count, 388 fill_seq_number, 372 m_smf0_channels_count, 388 fill_time_sig_and_tempo, 373 m_smf0_seq_number, 388 get, 370 m_smf0_seq_number, 388 m_position_for_get, 374 midisplitter, 385 ppqn, 387 split, 386 split_channel, 387 split_channel, 387 position_increment, 371 seq64::midi_timing, 388 beat_width, 390 beats_per_measure, 390 beats	_ ·	size, 381
start, 359 stop, 359 sysex, 362 seq64::midi_container, 367	set_ppqn, 357	seq64::midi_measures, 382
stop, 359 sysex, 362 seq64::midi_container, 367	set_sequence_input, 361	
sysex, 362 seq64::midi_container, 367	start, 359	divisions, 383
seq64::midi_container, 367 ~midi_container, 369 add_event, 372 add_long, 371 add_short, 372 add_variable, 371 clear, 371 done, 370 fill, 369 fill_meta_track_end, 373 fill_seq_number, 372 fill_seq_number, 372 fill_time_sig_and_tempo, 373 get, 370 m_osition_for_get, 374 midi_container, 369 midiffle, 374 position_reset, 371 position_reset, 371 position_reset, 371 seq64::midi_seq_event, 373 song_fill_seq_trigger, 374 m_beats_per_measure, 391 seq64::midi_control, 374 m_peats_per_minute, 391 m_peats_per_minute, 391 m_poets_per_minute, 391 m_popqn, 391	•	
~midi_container, 369 measures, 383 add_event, 372 midi_measures, 382 add_long, 371 seq64::midi_splitter, 384 add_short, 372 ~midi_splitter, 386 add_variable, 371 count, 387 clear, 371 increment, 386 done, 370 initialize, 386 fill, 369 log_main_sequence, 386 fill_meta_track_end, 373 m_ppqn, 388 fill_proprietary, 373 m_smf0_channels, 388 fill_seq_name, 372 m_smf0_channels_count, 388 fill_seq_number, 372 m_smf0_seq_number, 388 fill_time_sig_and_tempo, 373 m_smf0_seq_number, 388 get, 370 m_sequence, 374 m_sequence, 374 midi_splitter, 385 m_sequence, 374 ppqn, 387 midifile, 374 split_channel, 387 position_increment, 371 seq64::midi_timing, 388 beat_width, 390 beats_per_measure, 390 beats_per_measure, 390 size, 370 song_fill_seq_event, 373 m_beats_per_measure, 391 song_fill_seq_trigger, 374 m_beats_per_minute, 391 m_beats_per_minute, 391 m_beats_per_minute, 391	•	m_divisions, 384
add_event, 372 add_long, 371 add_short, 372 add_short, 372 add_variable, 371 clear, 371 clear, 371 done, 370 fill, 369 fill_meta_track_end, 373 fill_proprietary, 373 fill_seq_name, 372 fill_seq_number, 372 fill_seq_number, 372 fill_seq_number, 373 get, 370 m_sequence, 374 m_sequence, 374 midi_container, 369 midi_measures, 382 seq64::midi_splitter, 384 count, 387 count, 387 increment, 386 initialize, 386 log_main_sequence, 386 m_ppqn, 388 m_smf0_channels, 388 m_smf0_channels_count, 388 m_smf0_main_sequence, 388 m_smf0_seq_number, 388 m_smf0_seq_number, 388 m_seq64::midi_tipqn, 388 midi_splitter, 385 ppqn, 387 split_channel, 387 split_channel, 387 split_channel, 387 seq64::midi_timing, 388 beat_width, 390 beats_per_measure, 390 put, 370 song_fill_seq_event, 373 song_fill_seq_event, 373 song_fill_seq_trigger, 374 m_beats_per_measure, 391 m_beats_per_minute, 391 seq64::midi_control, 374	•	
add_long, 371 seq64::midi_splitter, 384 add_short, 372 ~midi_splitter, 386 add_variable, 371 count, 387 clear, 371 increment, 386 done, 370 initialize, 386 fill, 369 log_main_sequence, 386 fill_meta_track_end, 373 m_ppqn, 388 fill_seq_name, 372 m_smf0_channels, 388 fill_seq_number, 372 m_smf0_main_sequence, 388 fill_time_sig_and_tempo, 373 m_smf0_seq_number, 388 get, 370 m_use_default_ppqn, 388 m_position_for_get, 374 midi_splitter, 385 m_sequence, 374 ppqn, 387 midifile, 374 split, 386 position, 371 seq64:midi_timing, 388 position_increment, 371 beat_width, 390 position_reset, 371 beats_per_measure, 390 put, 370 m_beats_per_measure, 390 size, 370 m_beats_per_measure, 391 song_fill_seq_event, 373 m_beats_per_minute, 391 song_fill_seq_trigger, 374 m_peats_per_minute, 391 seq64::midi_control, 374 m_ppqn, 391		
add_short, 372 add_variable, 371 clear, 371 clear, 370 fill, 369 fill_meta_track_end, 373 fill_seq_name, 372 fill_seq_number, 372 fill_time_sig_and_tempo, 373 m_sequence, 374 midi_container, 369 midifile, 374 position_increment, 371 position_reset, 371 position_reset, 371 position_reset, 370 size, 370 song_fill_seq_trigger, 374 seq64::midi_control, 374 seq64::midi_control, 374 seq64::midi_control, 374 m_beats_per_minute, 391 seq64::midi_control, 374 m_popin, 381 count, 386 initialize, 386 log_main_sequence, 386 m_ppqn, 388 m_smf0_channels, 388 m_smf0_channels_count, 388 m_smf0_channels_count, 388 m_smf0_main_sequence, 388 m_smf0_seq_number, 388 m_smf0_seq_number, 388 m_use_default_ppqn, 388 midi_splitter, 385 m_use_default_ppqn, 388 split_channel, 387 seq64::midi_timing, 388 beat_width, 390 beats_per_measure, 390 m_beat_per_minute, 390 m_beat_per_minute, 391 m_ppqn, 391		
add_variable, 371 clear, 371 clear, 370 fill, 369 fill_meta_track_end, 373 fill_proprietary, 373 fill_seq_name, 372 fill_seq_number, 372 fill_time_sig_and_tempo, 373 m_sequence, 374 midi_container, 369 midifile, 374 position_increment, 371 position_reset, 371 position_reset, 371 position_reset, 370 size, 370 song_fill_seq_trigger, 374 seq64::midi_control, 374 seq64::midi_control, 374 m_beats_per_minute, 391 seq64::midi_control, 374 m_pogn, 381 m_count, 388 minitialize, 386 minitialize, 388 m_ppqn, 388 m_ppqn, 388 m_ppqn, 388 m_smf0_channels_count, 388 m_smf0_channels_count, 388 m_smf0_main_sequence, 388 m_smf0_seq_number, 388 m_seq6alult_ppqn, 388 midi_splitter, 385 m_use_default_ppqn, 388 midi_splitter, 385 split, 386 split_channel, 387 seq64::midi_timing, 388 beat_width, 390 beats_per_measure, 390 m_beat_sper_minute, 390 m_beat_per_minute, 391 m_ppqn, 391	_ •	. — .
clear, 371 done, 370 fill, 369 fill, 369 fill_meta_track_end, 373 fill_proprietary, 373 fill_seq_name, 372 fill_seq_number, 372 fill_time_sig_and_tempo, 373 get, 370 m_sequence, 374 midi_container, 369 midifile, 374 position_increment, 371 position_reset, 371 position_reset, 371 position_reset, 371 position_reset, 370 size, 370 song_fill_seq_event, 373 song_fill_seq_trigger, 374 micli_control, 374 seq64::midi_control, 374 midi_seq_number, 388 m_position_tor_get, 374 midi_splitter, 385 midi_splitter, 385 midi_splitter, 385 split_channel, 387 seq64::midi_timing, 388 beat_width, 390 beats_per_measure, 390 m_beat_sper_measure, 390 song_fill_seq_event, 373 song_fill_seq_event, 373 song_fill_seq_trigger, 374 m_ppqn, 391 initialize, 386 initialize, 386 m_ppqn, 388 m_sequence, 388 m_sequence, 388 m_seq0-channels, count, 388 m_smf0_channels, 388 m_smf0_channels_count, 388 m_smf0_		— ·
done, 370 fill, 369 fill, 369 fill_meta_track_end, 373 fill_proprietary, 373 fill_seq_name, 372 fill_seq_number, 372 fill_seq_number, 372 fill_time_sig_and_tempo, 373 get, 370 m_sequence, 374 midi_container, 369 midifile, 374 position, 371 position_increment, 371 position_reset, 371 position_reset, 371 song_fill_seq_event, 373 song_fill_seq_trigger, 374 seq64::midi_control, 374 seq64::midi_control, 374 seq64::midi_control, 374 midi_control, 374 midi_seq_trigger, 374 midi_seq_trig		
fill, 369 fill_meta_track_end, 373 fill_proprietary, 373 fill_seq_name, 372 fill_seq_number, 372 fill_seq_number, 372 fill_time_sig_and_tempo, 373 get, 370 m_sequence, 374 midi_container, 369 midifile, 374 position_increment, 371 position_reset, 371 put, 370 size, 370 song_fill_seq_trigger, 374 seq64::midi_control, 374 seq64::midi_control, 374 seq64::midi_control, 374 seq64::midi_control, 374 seq64::midi_control, 374 seq64::midi_control, 374 m_beats_per_minute, 391 m_ppqn, 381 m_pogn, 386 m_pogn, 387 seq64::midi_seq_eremeasure, 390 m_beats_per_measure, 390 m_beats_per_measure, 391 m_beats_per_minute, 391 seq64::midi_control, 374 m_ppqn, 391		ŕ
fill_meta_track_end, 373 fill_proprietary, 373 fill_seq_name, 372 fill_seq_number, 372 fill_seq_number, 372 fill_seq_number, 372 fill_time_sig_and_tempo, 373 get, 370 m_sequence, 374 midi_container, 369 midifile, 374 position_increment, 371 position_increment, 371 position_reset, 371 put, 370 size, 370 size, 370 song_fill_seq_event, 373 seq64::midi_control, 374 seq64::midi_control, 374 m_ppqn, 388 m_smf0_seq_number, 388 m_seq_number, 388 m_seq_number, 389 m_seq_number, 388 m_seq_n		•
fill_proprietary, 373 fill_seq_name, 372 fill_seq_number, 372 fill_seq_number, 372 fill_seq_number, 372 fill_seq_number, 372 fill_time_sig_and_tempo, 373 get, 370 m_smf0_channels_count, 388 m_smf0_main_sequence, 388 m_smf0_seq_number, 388 m_smf0_channels_count, 388 m_seq.acc, 374 position_spliter, 385 ppqn, 387 seq.acc, 370 seq.acc, 374 ppqn, 387 seq.acc, 374 seq.acc, 374 ppqn, 387 seq.acc, 374 seq.acc, 374 seq.acc, 374 seq.acc, 374 seq.acc, 374 seq.acc, 374 seq.		-
fill_seq_name, 372 fill_seq_number, 372 fill_seq_number, 372 fill_time_sig_and_tempo, 373 get, 370 m_smf0_main_sequence, 388 m_position_for_get, 374 midi_container, 369 midifile, 374 position_increment, 371 position_reset, 371 position_reset, 371 position_reset, 371 position_reset, 371 position_reset, 371 position_reset, 370 size, 370 size, 370 song_fill_seq_event, 373 song_fill_seq_trigger, 374 seq64::midi_control, 374 m_poats m_smf0_channels_count, 388 m_smf0_main_sequence, 388 m_sequence, 374 ppqn, 387 seq64::midi_seq_ender, 374 m_seq64::midi_seq_ender, 389 m_seq64::midi_seq_ender,		—
fill_seq_number, 372 fill_time_sig_and_tempo, 373 get, 370 m_smf0_seq_number, 388 m_position_for_get, 374 midi_container, 369 midifile, 374 position_increment, 371 position_reset, 371 position_reset, 371 position_reset, 371 position_reset, 371 seq64::midi_timing, 388 beat_width, 390 beats_per_measure, 390 beats_per_minute, 390 m_beat_width, 391 song_fill_seq_event, 373 seq64::midi_control, 374 m_beats_per_minute, 391 m_beats_per_minute, 391 m_beats_per_minute, 391 m_poqn, 391		
fill_time_sig_and_tempo, 373 get, 370 m_smf0_seq_number, 388 m_position_for_get, 374 midi_container, 369 midifile, 374 position, 371 position_increment, 371 position_reset, 371 position_res	_ <u>-</u>	
get, 370	_ ·	·
m_position_for_get, 374 m_sequence, 374 midi_container, 369 midifile, 374 position, 371 position_increment, 371 position_reset, 371 position_reset, 371 position_reset, 370 size, 370 song_fill_seq_trigger, 374 seq64::midi_timing, 388 beat_width, 390 beats_per_measure, 390 beats_per_minute, 390 m_beat_width, 391 m_beats_per_measure, 391 song_fill_seq_trigger, 374 seq64::midi_control, 374 m_ppqn, 391		,
m_sequence, 374 ppqn, 387 midi_container, 369 split, 386 midifile, 374 split_channel, 387 position, 371 seq64::midi_timing, 388 position_increment, 371 beat_width, 390 position_reset, 371 beats_per_measure, 390 put, 370 beats_per_minute, 390 size, 370 m_beat_width, 391 song_fill_seq_event, 373 m_beats_per_measure, 391 song_fill_seq_trigger, 374 m_peats_per_minute, 391 seq64::midi_control, 374 m_ppqn, 391	G .	
midi_container, 369 midifile, 374 position, 371 position_increment, 371 position_reset, 371 put, 370 size, 370 size, 370 song_fill_seq_trigger, 374 seq64::midi_control, 374 split_channel, 387 seq64::midi_timing, 388 beat_width, 390 beats_per_measure, 390 beats_per_minute, 390 m_beat_width, 391 m_beats_per_measure, 391 seq64::midi_control, 374 m_ppqn, 391	— — — — — — — — — — — — — — — — — — —	— <i>i</i>
midifile, 374 split_channel, 387 position, 371 seq64::midi_timing, 388 position_increment, 371 beat_width, 390 position_reset, 371 beats_per_measure, 390 put, 370 beats_per_minute, 390 size, 370 m_beat_width, 391 song_fill_seq_event, 373 m_beats_per_measure, 391 song_fill_seq_trigger, 374 m_beats_per_minute, 391 seq64::midi_control, 374 m_ppqn, 391	- •	
position, 371 seq64::midi_timing, 388 position_increment, 371 beat_width, 390 position_reset, 371 beats_per_measure, 390 put, 370 beats_per_minute, 390 size, 370 m_beat_width, 391 song_fill_seq_event, 373 m_beats_per_measure, 391 song_fill_seq_trigger, 374 m_beats_per_minute, 391 seq64::midi_control, 374 m_ppqn, 391	-	•
position_increment, 371 position_reset, 371 position_reset, 371 put, 370 put, 370 size, 370 song_fill_seq_event, 373 song_fill_seq_trigger, 374 seq64::midi_control, 374 beats_per_measure, 390 m_beats_width, 391 m_beats_per_measure, 391 m_beats_per_minute, 391 m_ppqn, 391		• —
position_reset, 371 beats_per_measure, 390 put, 370 beats_per_minute, 390 size, 370 m_beat_width, 391 song_fill_seq_event, 373 m_beats_per_measure, 391 song_fill_seq_trigger, 374 m_beats_per_minute, 391 seq64::midi_control, 374 m_ppqn, 391	•	
put, 370 beats_per_minute, 390 size, 370 m_beat_width, 391 song_fill_seq_event, 373 m_beats_per_measure, 391 song_fill_seq_trigger, 374 m_beats_per_minute, 391 seq64::midi_control, 374 m_ppqn, 391	• –	- · · · ·
size, 370 m_beat_width, 391 song_fill_seq_event, 373 m_beats_per_measure, 391 song_fill_seq_trigger, 374 m_beats_per_minute, 391 seq64::midi_control, 374 m_ppqn, 391	· –	<u> </u>
song_fill_seq_event, 373m_beats_per_measure, 391song_fill_seq_trigger, 374m_beats_per_minute, 391seq64::midi_control, 374m_ppqn, 391	•	—• —
song_fill_seq_trigger, 374 m_beats_per_minute, 391 seq64::midi_control, 374 m_ppqn, 391		
seq64::midi_control, 374 m_ppqn, 391	-	_ -
•		_ - _
active, 3/0 midi_timing, 389	•	—···
	active, 370	mu_uming, 309

ppqn, 391	error_is_fatal, 409
seq64::midi_vector, 392	error_message, 409
~midi_vector, 393	is_sysex_special_id, 420
CharVector, 393	m_char_list, 421
clear, 394	m_data, 421
done, 394	m_disable_reported, 421
get, 394	m_error_is_fatal, 421
m_char_vector, 395	m_error_message, 421
midi_vector, 393	m_file_size, 420
put, 394	m_global_bgsequence, 422
size, 394	m_mutex, 420
seq64::midibus, 395	m_name, 421
\sim midibus, 398	m_new_format, 422
clock, 400	m_pos, 421
continue_from, 400	m_ppqn, 422
deinit_in, 398	m_smf0_splitter, 422
flush, 401	m_use_default_ppqn, 422
get_client, 401	midifile, 406
get_clock, 401	parse, 407
get_clock_mod, 402	parse_prop_header, 410
get_id, 399	parse_proprietary_track, 411
get_input, 401	parse_smf_0, 409
get_name, 399	parse_smf_1, 409
get_port, 401	pow2, 411
init_clock, 400	ppqn, 409
init_in, 398	prop_item_size, 418
init_in_sub, 399	read_byte, 413
init_out, 398	read_byte_array, 414
init_out_sub, 398	read_long, 413
m_clock_mod, 402	read_seq_number, 416
m_clock_type, 402	read_short, 413
m_dest_addr_client, 402	read_track_name, 415
m_dest_addr_port, 403	read_varinum, 413
m_id, 402	seq_number_size, 420
m_inputing, 402	track_end_size, 420
m_lasttick, 403	track_name_size, 419
m_local_addr_client, 403	varinum_size, 418
m_local_addr_port, 403	write, 408
m_mutex, 403	write_byte, 414
m_name, 403	write_header, 416
m_ppqn, 402	write_long, 413
m_queue, 403	write_prop_header, 417
m seq, 402	write proprietary track, 417
mastermidibus, 402	write seg number, 415
midibus, 397	write short, 414
play, 399	write_song, 409
print, 399	write track, 420
set clock, 400	write track end, 416
set_clock_mod, 401	write_track_name, 415
set_input, 401	write varinum, 414
start, 400	seq64::mutex, 423
stop, 400	lock, 424
sysex, 399	m_mutex_lock, 424
seq64::midifile, 403	mutex, 424
~midifile, 407	sm recursive mutex, 424
add_trigger, 412	unlock, 424
checklen, 412	seq64::options, 425
errdump, 419	add_extended_keys_page, 429
Girduilip, 413	auu_exteriueu_keys_paye, 429

add_jack_sync_page, 429	m_button_play, 448
add_keyboard_page, 428	m_button_redo, 449
add_midi_clock_page, 428	m_button_snap, 448
add_midi_input_page, 428	m_button_stop, 448
add_mouse_page, 429	m_button_undo, 449
button, 426	m_button_xpose, 447
clock_callback_mod, 427	m_bw, 450
clock_callback_off, 427	m_entry_bpm, 449
clock_callback_on, 427	m_entry_bw, 449
clock_mod_callback, 427	m_entry_snap, 448
filter_callback, 427	m_entry_xpose, 447
input_callback, 427	m_hadjust, 447
lash_support_callback, 428	m_hbox, 449
m_button_jack_connect, 429	m_hlbox, 449
m_button_jack_disconnect, 430	m_hscroll, 447
m_button_jack_master, 429	m_image_play, 448
m_button_jack_master_cond, 429	m_is_running, 450
m_button_jack_transport, 429	m_menu_bpm, 450
m_button_ok, 429	m_menu_bw, 450
m_mainperf, 429	m_menu_snap, 447
m_notebook, 430	m_menu_xpose, 447
m_tooltips, 429	m_peer_perfedit, 446
mouse_fruity_callback, 428	m_perfnames, 447
mouse_mod4_callback, 428	m_perfroll, 447
mouse_seq24_callback, 428	m_perftime, 447
mouse_snap_split_callback, 428	m_ppqn, 450
options, 427	m_snap, 450
perf, 427	m_standard_bpm, 450
transport_callback, 428	m_table, 446
seq64::optionsfile, 430	m_tooltips, 450
\sim optionsfile, 431	m_vadjust, 446
error_message, 434	m_vscroll, 447
optionsfile, 431	on_delete_event, 446
parse, 431	on_key_press_event, 445
write, 433	on_realize, 445
seq64::perfedit, 434	pause_playing, 445
\sim perfedit, 440	perfedit, 439
collapse, 443	popup_menu, 444
copy, 444	redo, 444
draw_sequences, 444	rewind, 441
enqueue_draw, 440	set_beat_width, 442
enregister_peer, 440	set_beats_per_bar, 442
expand, 443	set_follow_transport, 441
FF_RW_timeout, 446	set_guides, 443
fast_forward, 441	set_image, 444
get_toggle_jack, 441	set_jack_mode, 442
grow, 443	set_looped, 443
init_before_show, 440	set_snap, 443
m_bpm, 450	set_transpose, 442
m button bpm, 449	set zoom, 441
m_button_bw, 449	start_playing, 445
m_button_collapse, 448	stop_playing, 445
m_button_copy, 448	timeout, 444
m button expand, 448	toggle_follow_transport, 441
m_button_follow, 449	toggle_jack, 441
m_button_grow, 448	toggle_playing, 445
m button jack, 449	transpose button callback, 442
m_button_loop, 448	undo, 444
<u></u>	- 1.000, 1.11

update_perfedit_sequences, 446	filter_by_channel, 475
zoom_check, 440	finish, 482
seq64::perfnames, 451	get_32nds_per_quarter, 474
\sim perfnames, 454	get_beat_width, 474
change_vert, 455	get_beats_per_bar, 473
convert_y, 454	get_beats_per_minute, 484
draw_sequence, 454	get_current_jack_position, 519
draw_sequences, 454	get_follow_transport, 478
enqueue_draw, 454	get_group_mute_state, 488
m_char_w, 457	get_jack_tick, 482
m namebox w, 458	get_key_events, 489
m_names_chars, 457	get_key_events_rev, 489
m_names_x, 458	get_key_groups, 489
m_names_y, 458	get_key_groups_rev, 489
m_parent, 457	get_left_tick, 482
m_seqs_in_set, 458	get_max_trigger, 501
m_sequence_active, 458	get_offset, 488
m_sequence_max, 458	get_playing_screenset, 500
m_sequence_offset, 458	get_right_tick, 483
m_setbox_w, 457	get_screen_set_notepad, 503
m_xy_offset, 458	get screenset, 500
on button press event, 456	get_sequence, 494
on_button_release_event, 456	
	get_start_tick, 483
on_expose_event, 455	get_tick, 482
on_realize, 455	get_toggle_jack, 477
on_scroll_event, 457	get_transpose, 484
on_size_allocate, 456	gui, 475
perfedit, 457	handle_midi_control, 502
perfnames, 453	have_redo, 501
redraw, 455	have_undo, 500
redraw_dirty_sequences, 454	highlight, 494
seq64::perform, 459	increment_beats_per_minute, 493
~perform, 472	increment_screenset, 494
add_sequence, 480	init_jack, 510
all_notes_off, 508	inner_start, 514
any_group_unmutes, 504	inner_stop, 514
apply_song_transpose, 484	input_func, 487
armed_saved, 486	input_thread_func, 516
clamp_track, 514	install_sequence, 513
clear_all, 479	is_active, 483
clear_sequence_triggers, 481	is_control_status, 473
clocks_per_metronome, 474	is_dirty_edit, 499
collapse, 501	is_dirty_main, 498
combine_bytes, 477	is_dirty_names, 499
copy, 501	is_dirty_perf, 499
copy_triggers, 498	is_edit_sequence, 473
current_screen_set_notepad, 503	is_exportable, 500
decrement_beats_per_minute, 493	is_group_learning, 506
decrement_screenset, 493	is_jack_master, 476
deinit_jack, 510	is_jack_running, 476
delete_sequence, 481	is_modified, 472, 511
enregister, 476	is_mseq_valid, 513
expand, 501	is_pattern_playing, 475, 512
FF_RW_timeout, 477	is_running, 475
FF_rewind, 477	is_screenset_valid, 511
fast_forward, 479	is_seq_valid, 512
ff_rw_button_t, 471	is_sequence_in_edit, 481
ff_rw_type, 478	is_smf_0, 494

jack_assistant, 516	m_outputing, 523
jack_process_callback, 518	m_playback_mode, 523
jack_shutdown, 518	m_playing_screen, 521
jack_sync_callback, 517	m_playscreen_offset, 521
jack_timebase_callback, 518	m_ppqn, 524
key_name, 489	m_redo_vect, 528
keybindentry, 516	m_reposition, 520
keys, 475	m_right_tick, 525
launch, 479	m_running, 523
launch_input_thread, 510	m_screen_set_notepad, 526
launch_output_thread, 510	m_screenset, 526
learn_toggle, 493	m seqs, 521
left_right_size, 483	m_seqs_active, 521
lookup_keyevent_key, 490	m_seqs_in_set, 527
lookup_keyevent_seq, 490	m_sequence_count, 527
lookup_keygroup_group, 491	m_sequence_max, 527
lookup_keygroup_key, 491	m_sequence_state, 522
m_32nds_per_quarter, 524	m_song_start_mode, 519
m_FF_RW_button_type, 520	m_start_from_perfedit, 519
m_armed_saved, 520	m_starting_tick, 525
m_armed_statuses, 520	m tick, 525
m_beat_width, 524	m_tracks_mute_state, 520
m_beats_per_bar, 524	m_transpose, 522
m_clocks_per_metronome, 524	m_undo_vect, 528
m_condition_var, 527	m_us_per_quarter_note, 524
m_control_status, 526	m_usemidiclock, 525
m dont reset ticks, 526	m_was_active_edit, 522
m_edit_sequence, 527	m_was_active_edit, 522 m_was_active_main, 521
m_excell_FF_RW, 520	m_was_active_names, 522
m_gui_support, 520	m_was_active_perf, 522
m_have_redo, 528	mainwnd, 516
m_have_undo, 528	mainwind, 310
m_in_thread, 522	master bus, 475
m_in_thread_launched, 523	max active set, 510
m_inputing, 523	midi control off, 502
m_is_modified, 527	midi_control_on, 502
m_is_pattern_playing, 523	midi_control_toggle, 502
m_jack_asst, 528	midifile, 516
m_jack_tick, 525	modify, 472
m_left_tick, 525	move_triggers, 497
m looping, 523	mute_all_tracks, 486
m_master_bus, 522	mute_group_offset, 512
	_ -
m_max_sets, 527	mute_group_tracks, 504
m_midi_cc_off, 526	mute_op_t, 471
m_midi_cc_on, 526	mute_screenset, 486
m_midi_cc_toggle, 526	new_sequence, 480
m_midiclockpos, 526	off_sequences, 507
m_midiclockrunning, 525	options, 516
m_midiclocktick, 525	optionsfile, 516
m_mode_group, 520	output_func, 487
m_mode_group_learn, 521	output_thread_func, 517
m_mute_group, 520	pause_key, 493
m_mute_group_selected, 521	pause_playing, 492
m_notify, 528	perfedit, 516
m_offset, 526	perform, 472
m_one_measure, 524	perfroll, 516
m_out_thread, 522	perfroll_key_event, 496
m_out_thread_launched, 523	play, 509

playback_key_event, 497	set_was_active, 508
pop_trigger_redo, 498	show_ui_sequence_key, 489
pop_trigger_undo, 498	show_ui_sequence_number, 490
position_jack, 507	sm_mc_dummy, 519
print_triggers, 481	song_start_mode, 476
push_trigger_undo, 498	split_trigger, 501
reposition, 479	start, 506
reset_sequences, 508	start_from_perfedit, 478
restore_playing_state, 488	start_jack, 507
rewind, 478	start_key, 492
save_playing_state, 488	start_playing, 491
select_and_mute_group, 504	stop, 506
select_group_mute, 505	stop_jack, 507
seq_in_playing_screen, 510	stop_key, 493
sequence_count, 472	stop_playing, 492
sequence_key, 495	toggle_all_tracks, 486
sequence_label, 495	toggle_follow_transport, 478
sequence_max, 472	toggle jack mode, 476
sequence_playing_change, 485	toggle_playing_tracks, 486
sequence_playing_off, 485	toggle_song_start_mode, 475
sequence_playing_on, 485	unset_edit_sequence, 473
sequence_playing_toggle, 485	unset_mode_group_learn, 506
set_32nds_per_quarter, 474	unset_mode_group_mute, 505
set_active, 508	unset_sequence_control_status, 485
set_all_key_events, 515	us_per_quarter_note, 474, 475
set_all_key_groups, 515	valid_midi_control_seq, 511
set_and_copy_mute_group, 506	seq64::performcallback, 529
set_beat_width, 474	on_grouplearnchange, 530
set_beats_per_bar, 474	seq64::perfroll, 530
set_beats_per_minute, 509	~perfroll, 535
set_edit_sequence, 473	change_horz, 539
set_follow_transport, 478	change_vert, 539
set_group_mute_state, 487	convert_drop_xy, 539
set_have_redo, 501	convert x, 538
set have undo, 500	convert_xy, 537
set input bus, 496	draw_all, 536
set_jack_mode, 476	draw_background_on, 538
set_jack_stop_tick, 477	draw drawable row, 538
set jack tick, 482	draw progress, 537
set_key_event, 515	draw_sequence_on, 538
set_key_group, 515	enqueue_draw, 539
set_left_tick, 482	fill_background_pixmap, 536
set_looping, 509	follow_progress, 536
set mode group learn, 505	FruityPerfInput, 544
set mode group mute, 505	horizontal_adjust, 540
set_offset, 488	horizontal set, 541
set_orig_ticks, 509	increment size, 536
set_playback_mode, 512	init_before_show, 536
set_playing_screenset, 504	m_4bar_offset, 546
set_reposition, 478	m_background_x, 545
set_right_tick, 483	m_beat_length, 546
set_running, 512	m_divs_per_beat, 545
set_screen_set_notepad, 503, 504	m_drop_sequence, 547
set screenset, 500	m_drop_tick, 547
set_sequence_control_status, 484	m_drop_tick_trigger_offset, 547
set_song_mute, 505	m_fruity_interaction, 547
set_start_tick, 483	m_grow_direction, 548
set_transpose, 484	m_growing, 548
001_110p000, 101	III_growing, 570

m_h_page_increment, 544	m_left_marker_tick, 557
m_have_button_press, 546	m_measure_length, 557
m_interaction, 548	m_parent, 557
m_measure_length, 546	m_perf_scale_x, 558
m moving, 548	m_ppqn, 557
m_names_y, 545	m_right_marker_tick, 558
m_old_progress_ticks, 546	m_snap, 557
m page factor, 545	m_tick_offset, 557
m_parent, 544	m_timearea_y, 558
m_perf_scale_x, 545	on_button_press_event, 555
m_ppqn, 545	on_button_release_event, 556
m_roll_length_ticks, 547	on_expose_event, 555
	_ · _
m_seq24_interaction, 548	on_realize, 555
m_sequence_active, 547	on_size_allocate, 556
m_sequence_max, 547	perfedit, 557
m_sequence_offset, 546	perftime, 551
m_size_box_w, 545	pixel_to_tick, 554
m_snap, 544	reset, 552
m_ticks_per_bar, 545	set_guides, 552
m_trans_button_press, 546	set_ppqn, 553
m_transport_follow, 546	set_scale, 552
m_v_page_increment, 544	set_zoom, 553
m_zoom, 545	tick_offset, 554
on_button_press_event, 542	tick_to_pixel, 554
on_button_release_event, 542	update_pixmap, 554
on_expose_event, 542	update_sizes, 554
on focus in event, 543	seq64::rc settings, 558
on_focus_out_event, 543	allow_mod4_mode, 564, 566
on_key_press_event, 543	allow_snap_split, 564, 567
on_motion_notify_event, 542	auto_option_save, 563, 566
on realize, 541	config_directory, 566, 569
on scroll event, 542	config_filename, 566, 570
on_size_allocate, 543	config_filename_alt, 566, 570
on size request, 544	config_filespec, 563
perfedit, 544	device_ignore, 565, 568
•	device_ignore, 303, 300
	dovice ignere num EGE EGO
perfroll, 535	device_ignore_num, 565, 568
redraw_dirty_sequences, 537	filename, 565, 569
redraw_dirty_sequences, 537 redraw_progress, 536	filename, 565, 569 filter_by_channel, 565, 567
redraw_dirty_sequences, 537 redraw_progress, 536 Seq24PerfInput, 544	filename, 565, 569 filter_by_channel, 565, 567 help_check, 572
redraw_dirty_sequences, 537 redraw_progress, 536 Seq24PerfInput, 544 set_guides, 535	filename, 565, 569 filter_by_channel, 565, 567 help_check, 572 home_config_directory, 570
redraw_dirty_sequences, 537 redraw_progress, 536 Seq24PerfInput, 544 set_guides, 535 set_ppqn, 537	filename, 565, 569 filter_by_channel, 565, 567 help_check, 572 home_config_directory, 570 interaction_method, 565, 568
redraw_dirty_sequences, 537 redraw_progress, 536 Seq24PerfInput, 544 set_guides, 535 set_ppqn, 537 set_zoom, 539	filename, 565, 569 filter_by_channel, 565, 567 help_check, 572 home_config_directory, 570 interaction_method, 565, 568 jack_session_uuid, 565, 569
redraw_dirty_sequences, 537 redraw_progress, 536 Seq24PerfInput, 544 set_guides, 535 set_ppqn, 537 set_zoom, 539 snap_x, 538	filename, 565, 569 filter_by_channel, 565, 567 help_check, 572 home_config_directory, 570 interaction_method, 565, 568 jack_session_uuid, 565, 569 lash_support, 564, 566
redraw_dirty_sequences, 537 redraw_progress, 536 Seq24PerfInput, 544 set_guides, 535 set_ppqn, 537 set_zoom, 539 snap_x, 538 split_trigger, 539	filename, 565, 569 filter_by_channel, 565, 567 help_check, 572 home_config_directory, 570 interaction_method, 565, 568 jack_session_uuid, 565, 569 lash_support, 564, 566 last_used_dir, 566, 569
redraw_dirty_sequences, 537 redraw_progress, 536 Seq24PerfInput, 544 set_guides, 535 set_ppqn, 537 set_zoom, 539 snap_x, 538	filename, 565, 569 filter_by_channel, 565, 567 help_check, 572 home_config_directory, 570 interaction_method, 565, 568 jack_session_uuid, 565, 569 lash_support, 564, 566
redraw_dirty_sequences, 537 redraw_progress, 536 Seq24PerfInput, 544 set_guides, 535 set_ppqn, 537 set_zoom, 539 snap_x, 538 split_trigger, 539	filename, 565, 569 filter_by_channel, 565, 567 help_check, 572 home_config_directory, 570 interaction_method, 565, 568 jack_session_uuid, 565, 569 lash_support, 564, 566 last_used_dir, 566, 569
redraw_dirty_sequences, 537 redraw_progress, 536 Seq24PerfInput, 544 set_guides, 535 set_ppqn, 537 set_zoom, 539 snap_x, 538 split_trigger, 539 update_sizes, 535	filename, 565, 569 filter_by_channel, 565, 567 help_check, 572 home_config_directory, 570 interaction_method, 565, 568 jack_session_uuid, 565, 569 lash_support, 564, 566 last_used_dir, 566, 569 legacy_format, 563, 566
redraw_dirty_sequences, 537 redraw_progress, 536 Seq24PerfInput, 544 set_guides, 535 set_ppqn, 537 set_zoom, 539 snap_x, 538 split_trigger, 539 update_sizes, 535 vertical_adjust, 541	filename, 565, 569 filter_by_channel, 565, 567 help_check, 572 home_config_directory, 570 interaction_method, 565, 568 jack_session_uuid, 565, 569 lash_support, 564, 566 last_used_dir, 566, 569 legacy_format, 563, 566 m_allow_mod4_mode, 572
redraw_dirty_sequences, 537 redraw_progress, 536 Seq24PerfInput, 544 set_guides, 535 set_ppqn, 537 set_zoom, 539 snap_x, 538 split_trigger, 539 update_sizes, 535 vertical_adjust, 541 vertical_set, 541	filename, 565, 569 filter_by_channel, 565, 567 help_check, 572 home_config_directory, 570 interaction_method, 565, 568 jack_session_uuid, 565, 569 lash_support, 564, 566 last_used_dir, 566, 569 legacy_format, 563, 566 m_allow_mod4_mode, 572 m_allow_snap_split, 572
redraw_dirty_sequences, 537 redraw_progress, 536 Seq24PerfInput, 544 set_guides, 535 set_ppqn, 537 set_zoom, 539 snap_x, 538 split_trigger, 539 update_sizes, 535 vertical_adjust, 541 vertical_set, 541 seq64::perftime, 549	filename, 565, 569 filter_by_channel, 565, 567 help_check, 572 home_config_directory, 570 interaction_method, 565, 568 jack_session_uuid, 565, 569 lash_support, 564, 566 last_used_dir, 566, 569 legacy_format, 563, 566 m_allow_mod4_mode, 572 m_allow_snap_split, 572 m_auto_option_save, 572
redraw_dirty_sequences, 537 redraw_progress, 536 Seq24PerfInput, 544 set_guides, 535 set_ppqn, 537 set_zoom, 539 snap_x, 538 split_trigger, 539 update_sizes, 535 vertical_adjust, 541 vertical_set, 541 seq64::perftime, 549 ~perftime, 552	filename, 565, 569 filter_by_channel, 565, 567 help_check, 572 home_config_directory, 570 interaction_method, 565, 568 jack_session_uuid, 565, 569 lash_support, 564, 566 last_used_dir, 566, 569 legacy_format, 563, 566 m_allow_mod4_mode, 572 m_allow_snap_split, 572 m_auto_option_save, 572 m_config_directory, 574
redraw_dirty_sequences, 537 redraw_progress, 536 Seq24PerfInput, 544 set_guides, 535 set_ppqn, 537 set_zoom, 539 snap_x, 538 split_trigger, 539 update_sizes, 535 vertical_adjust, 541 vertical_set, 541 seq64::perftime, 549 ~perftime, 552 change_horz, 553	filename, 565, 569 filter_by_channel, 565, 567 help_check, 572 home_config_directory, 570 interaction_method, 565, 568 jack_session_uuid, 565, 569 lash_support, 564, 566 last_used_dir, 566, 569 legacy_format, 563, 566 m_allow_mod4_mode, 572 m_allow_snap_split, 572 m_auto_option_save, 572 m_config_directory, 574 m_config_filename, 574
redraw_dirty_sequences, 537 redraw_progress, 536 Seq24PerfInput, 544 set_guides, 535 set_ppqn, 537 set_zoom, 539 snap_x, 538 split_trigger, 539 update_sizes, 535 vertical_adjust, 541 vertical_set, 541 seq64::perftime, 549 ~perftime, 552 change_horz, 553 draw_background, 553	filename, 565, 569 filter_by_channel, 565, 567 help_check, 572 home_config_directory, 570 interaction_method, 565, 568 jack_session_uuid, 565, 569 lash_support, 564, 566 last_used_dir, 566, 569 legacy_format, 563, 566 m_allow_mod4_mode, 572 m_allow_snap_split, 572 m_auto_option_save, 572 m_config_directory, 574 m_config_filename_alt, 575
redraw_dirty_sequences, 537 redraw_progress, 536 Seq24PerfInput, 544 set_guides, 535 set_ppqn, 537 set_zoom, 539 snap_x, 538 split_trigger, 539 update_sizes, 535 vertical_adjust, 541 vertical_set, 541 seq64::perftime, 549 ~perftime, 552 change_horz, 553 draw_pixmap_on_window, 555 draw_progress_on_window, 553	filename, 565, 569 filter_by_channel, 565, 567 help_check, 572 home_config_directory, 570 interaction_method, 565, 568 jack_session_uuid, 565, 569 lash_support, 564, 566 last_used_dir, 566, 569 legacy_format, 563, 566 m_allow_mod4_mode, 572 m_allow_snap_split, 572 m_auto_option_save, 572 m_config_directory, 574 m_config_filename, 574 m_config_filename_alt, 575 m_device_ignore_num, 574
redraw_dirty_sequences, 537 redraw_progress, 536 Seq24PerfInput, 544 set_guides, 535 set_ppqn, 537 set_zoom, 539 snap_x, 538 split_trigger, 539 update_sizes, 535 vertical_adjust, 541 vertical_set, 541 seq64::perftime, 549 ~perftime, 552 change_horz, 553 draw_background, 553 draw_pixmap_on_window, 555 draw_progress_on_window, 553 enqueue_draw, 552	filename, 565, 569 filter_by_channel, 565, 567 help_check, 572 home_config_directory, 570 interaction_method, 565, 568 jack_session_uuid, 565, 569 lash_support, 564, 566 last_used_dir, 566, 569 legacy_format, 563, 566 m_allow_mod4_mode, 572 m_allow_snap_split, 572 m_auto_option_save, 572 m_config_directory, 574 m_config_filename, 574 m_config_filename_alt, 575 m_device_ignore, 574 m_filename, 574
redraw_dirty_sequences, 537 redraw_progress, 536 Seq24PerfInput, 544 set_guides, 535 set_ppqn, 537 set_zoom, 539 snap_x, 538 split_trigger, 539 update_sizes, 535 vertical_adjust, 541 vertical_set, 541 seq64::perftime, 549 ~perftime, 552 change_horz, 553 draw_background, 553 draw_pixmap_on_window, 555 draw_progress_on_window, 553 enqueue_draw, 552 idle_progress, 554	filename, 565, 569 filter_by_channel, 565, 567 help_check, 572 home_config_directory, 570 interaction_method, 565, 568 jack_session_uuid, 565, 569 lash_support, 564, 566 last_used_dir, 566, 569 legacy_format, 563, 566 m_allow_mod4_mode, 572 m_allow_snap_split, 572 m_auto_option_save, 572 m_config_directory, 574 m_config_filename, 574 m_config_filename_alt, 575 m_device_ignore, 574 m_filename, 574 m_filename, 574 m_filter_by_channel, 573
redraw_dirty_sequences, 537 redraw_progress, 536 Seq24PerfInput, 544 set_guides, 535 set_ppqn, 537 set_zoom, 539 snap_x, 538 split_trigger, 539 update_sizes, 535 vertical_adjust, 541 vertical_set, 541 seq64::perftime, 549 ~perftime, 552 change_horz, 553 draw_background, 553 draw_pixmap_on_window, 555 draw_progress_on_window, 553 enqueue_draw, 552 idle_progress, 554 increment_size, 552	filename, 565, 569 filter_by_channel, 565, 567 help_check, 572 home_config_directory, 570 interaction_method, 565, 568 jack_session_uuid, 565, 569 lash_support, 564, 566 last_used_dir, 566, 569 legacy_format, 563, 566 m_allow_mod4_mode, 572 m_allow_snap_split, 572 m_auto_option_save, 572 m_config_directory, 574 m_config_filename_alt, 575 m_device_ignore, 574 m_filename, 574 m_filename, 574 m_filter_by_channel, 573 m_interaction_method, 574
redraw_dirty_sequences, 537 redraw_progress, 536 Seq24PerfInput, 544 set_guides, 535 set_ppqn, 537 set_zoom, 539 snap_x, 538 split_trigger, 539 update_sizes, 535 vertical_adjust, 541 vertical_set, 541 seq64::perftime, 549 ~perftime, 552 change_horz, 553 draw_background, 553 draw_pixmap_on_window, 555 draw_progress_on_window, 553 enqueue_draw, 552 idle_progress, 554	filename, 565, 569 filter_by_channel, 565, 567 help_check, 572 home_config_directory, 570 interaction_method, 565, 568 jack_session_uuid, 565, 569 lash_support, 564, 566 last_used_dir, 566, 569 legacy_format, 563, 566 m_allow_mod4_mode, 572 m_allow_snap_split, 572 m_auto_option_save, 572 m_config_directory, 574 m_config_filename, 574 m_config_filename_alt, 575 m_device_ignore, 574 m_filename, 574 m_filename, 574 m_filter_by_channel, 573

m_last_used_dir, 574	m_old, 593
m_legacy_format, 572	m_scroll_offset_ticks, 592
m_manual_alsa_ports, 573	m_scroll_offset_x, 592
m_pass_sysex, 573	m_seq, 592
m_print_keys, 573	m_status, 592
m_priority, 573	m_zoom, 592
m_reveal_alsa_ports, 573	on_button_press_event, 589
m_show_midi, 572	on_button_release_event, 590
m_stats, 573	on_expose_event, 589
m_user_filename, 574	on_leave_notify_event, 590
m_user_filename_alt, 575	on_motion_notify_event, 590
m_with_jack_master, 573	on_realize, 589
m_with_jack_master_cond, 573	on_scroll_event, 590
m_with_jack_transport, 573	on_size_allocate, 591
mainwnd, 571	redraw, 586
manual_alsa_ports, 565, 568	render_number, 588
operator=, 563	reset, 586
options, 571	seqdata, 585
optionsfile, 571	segevent, 591
parse_command_line_options, 571	segroll, 591
pass_sysex, 564, 567	set_data_type, 586
print_keys, 565, 568	set zoom, 586
priority, 564, 567	update pixmap, 587
rc_settings, 562	update_sizes, 587
reveal_alsa_ports, 565, 568	xy_to_rect, 587
set_config_files, 569	seq64::seqedit, 593
set_defaults, 563	\sim seqedit, 601
show_midi, 564, 567	apply_length, 604
stats, 564, 567	change_focus, 609
user_filename, 566, 570	create_menu_image, 609
user_filename_alt, 566, 570	create_menus, 607
user_filespec, 563	do_action, 609
with_jack, 565	fill_top_bar, 607
with_jack_master, 564, 567	get_measures, 604
with_jack_master_cond, 564, 567	handle_close, 610
with_jack_transport, 564, 567	horizontal_adjust, 603
seq64::rect, 575	horizontal_set, 603
height, 575	m_bgsequence, 613
width, 575	m_button_bpm, 620
x, 575	m_button_bus, 618
y, 575	m_button_bw, 620
seq64::seqdata, 582	m_button_channel, 618
\sim seqdata, 586	m_button_chord, 619
change_horz, 588	m_button_data, 620
convert_x, 588	m_button_key, 619
draw_events_on, 588	m_button_length, 619
draw_events_on_pixmap, 589	m_button_lfo, 615
draw_line_on_window, 587	m_button_note_length, 618
draw_pixmap_on_window, 589	m_button_quantize, 617
idle_redraw, 587	m_button_rec_vol, 620
Ifownd, 591	m_button_redo, 617
m_cc, 592	m_button_scale, 619
m_drag_handle, 593	m_button_sequence, 618
m_dragging, 593	m_button_snap, 618
m_number_h, 592	m_button_tools, 618
m_number_offset_y, 592	m_button_undo, 617
m_number_w, 592	m_button_zoom, 619
m_numbers, 593	m_chord, 613

m_editing_cc, 621	m_table, 617
m_editing_status, 621	m_toggle_play, 620
m_entry_bpm, 620	m_toggle_q_rec, 621
m_entry_bus, 618	m_toggle_record, 621
m_entry_bw, 620	m_toggle_thru, 621
m_entry_channel, 618	m_toggle_transpose, 614
m_entry_chord, 620	m_tooltips, 620
m_entry_data, 620	m_vadjust, 616
m_entry_key, 619	m_vbox, 617
m_entry_length, 619	m_vscroll_new, 616
m_entry_name, 621	m_zoom, 612
m entry note length, 619	mouse action, 609
m_entry_scale, 619	name_change_callback, 606
m_entry_sequence, 618	on delete event, 610
m_entry_snap, 618	on_focus_in_event, 610
m_entry_zoom, 619	on_focus_out_event, 610
m hadjust, 616	on_key_press_event, 611
m have focus, 621	on_realize, 610
m hbox, 617	on scroll event, 610
_ · · · ·	on set focus, 610
m_hbox2, 617	
m_hscroll_new, 616	play_change_callback, 606
m_image_transpose, 614	popup_event_menu, 608
m_initial_chord, 612	popup_menu, 608
m_initial_note_length, 612	popup_midibus_menu, 608
m_initial_snap, 612	popup_midich_menu, 609
m_initial_zoom, 612	popup_sequence_menu, 608
m_key, 613	popup_tool_menu, 608
m_lfo_wnd, 616	q_rec_change_callback, 606
m_measures, 613	record_change_callback, 606
m_menu_bpm, 615	redo_callback, 607
m_menu_bw, 615	seqedit, 601
m_menu_chords, 615	seqmenu, 612
m_menu_data, 615	set_background_sequence, 605
m_menu_key, 615	set_beat_width, 602
m_menu_length, 614	set_beats_per_bar, 602
m_menu_midibus, 615	set_chord, 605
m_menu_midich, 615	set_data_type, 607
m_menu_note_length, 614	set_key, 605
m_menu_rec_vol, 616	set_measures, 604
m menu scale, 615	set_midi_bus, 605
m_menu_sequences, 615	set_midi_channel, 604
m_menu_snap, 614	set_note_length, 602
m_menu_tools, 614	set_rec_vol, 603
m_menu_zoom, 614	set_scale, 605
m_menubar, 614	set snap, 601
m_note_length, 613	set_transpose_image, 602
-	_ · · _ ·
m_pp_eighth, 613	set_zoom, 601
m_pp_sixteenth, 614	start_playing, 609
m_pp_whole, 613	stop_playing, 609
m_ppqn, 613	thru_change_callback, 606
m_scale, 613	timeout, 609
m_seq, 614	transpose_change_callback, 606
m_seqdata_wid, 616	undo_callback, 606
m_seqevent_wid, 617	update_all_windows, 607
m_seqkeys_wid, 616	vertical_adjust, 603
m_seqroll_wid, 617	vertical_set, 604
m_seqtime_wid, 616	seq64::seqevent, 622
m_snap, 613	\sim seqevent, 625

change_horz, 629	draw_area, 640
convert_t, 629	draw_key, 641
convert_x, 629	force_draw, 640
draw_background, 627	FruitySeqRollInput, 644
draw_events_on, 628	is black key, 641
draw_events_on_pixmap, 627	m_hint_key, 645
draw_pixmap_on_window, 627	m_hint_state, 644
draw_selection_on_window, 627	m_key, 645
drop event, 628	m_keying, 645
force_draw, 627	m_keying_note, 645
FruitySeqEventInput, 633	m_scale, 645
idle_redraw, 627	m_scroll_offset_key, 644
	m_scroll_offset_y, 644
m_cc, 635	_
m_fruity_interaction, 633	m_seq, 644
m_growing, 634	m_show_octave_letters, 645
m_move_snap_offset_x, 635	on_button_press_event, 642
m_moving, 634	on_button_release_event, 642
m_moving_init, 634	on_enter_notify_event, 643
m_old, 634	on_expose_event, 642
m_painting, 635	on_leave_notify_event, 643
m_paste, 635	on_motion_notify_event, 643
m_ppqn, 633	on_realize, 642
m_scroll_offset_ticks, 634	on_scroll_event, 643
m_scroll_offset_x, 634	on_size_allocate, 644
m_selected, 634	reset, 641
m_selecting, 634	seqkeys, 638
m seq, 633	segroll, 644
m_seq24_interaction, 633	set_hint_key, 639
m_seqdata_wid, 634	set_hint_state, 639
m_snap, 633	set_key, 639
m_status, 635	set listen button press, 640
m zoom, 633	set_listen_button_release, 640
on button press event, 630	set_listen_motion_notify, 640
	-
on_button_release_event, 631	set_scale, 639
on_expose_event, 630	update_pixmap, 640
on_focus_in_event, 632	update_sizes, 641
on_focus_out_event, 632	seq64::seqmenu, 646
on_key_press_event, 632	∼seqmenu, 649
on_motion_notify_event, 631	current_seq, 649
on_realize, 630	delete_current_sequence, 651
on_size_allocate, 632	get_current_sequence, 650
redraw, 626	get_sequence, 650
reset, 626	is_current_seq_active, 650
Seq24SeqEventInput, 633	is_current_seq_in_edit, 650
seqevent, 625	is_edit_sequence, 650
set_data_type, 626	is_modified, 649, 650
set_snap, 626	m_clipboard, 654
set_zoom, 626	m_current_seq, 654
snap_x, 630	m_eventedit, 654
snap_y, 629	m_mainperf, 654
start_paste, 629	m menu, 654
update_pixmap, 627	m_modified, 654
update_sizes, 626	m_seqedit, 654
x_to_w, 628	mainwnd, 654
seq64::seqkeys, 636	mute_all_tracks, 653
~seqkeys, 639	new_current_sequence, 650
change_vert, 641	now_current_sequence, 000
	new sequence 650
convert_y, 640	new_sequence, 650 on_realize, 653

251	
popup_menu, 651	m_fruity_interaction, 680
redraw, 652	m_growing, 682
seq_clear_perf, 653	m_horizontal_adjust, 680
seq_copy, 652	m_is_drag_pasting, 682
seq_cut, 652	m_is_drag_pasting_start, 682
seq_edit, 651	m_justselected_one, 682
seq_event_edit, 651	m_key, <mark>68</mark> 1
seq_new, 652	m_move_delta_x, 682
seq_paste, 652	m_move_delta_y, 683
seq_set_and_edit, 651	m_move_snap_offset_x, 683
seq_set_and_eventedit, 652	m_moving, 682
seqmenu, 649	m_moving_init, 682
set_bus_and_midi_channel, 653	m_note_length, 681
set_edit_sequence, 649	m_old, 680
set_transposable, 653	m_painting, 682
toggle_all_tracks, 653	m_paste, 682
toggle_current_sequence, 651	m_pos, 680
unmute_all_tracks, 653	m_ppqn, 681
unset edit sequence, 650	m_progress_x, 683
seq64::seqroll, 655	m_scale, 681
∼segroll, 661	m_scroll_offset_key, 683
add_chord, 662	m_scroll_offset_ticks, 683
add_note, 662	m scroll offset x, 683
adding, 675	m_scroll_offset_y, 683
align_selection, 672	m_selected, 680
button_press, 673	m_selecting, 681
button_press_initial, 672	m seq, 680
button_release, 673	m_seqkeys_wid, 680
change_horz, 670	m_snap, 681
change_vert, 670	m_status, 684
clear_flags, 674	m_trans_button_press, 683
clear_old, 674	m_transport_follow, 683
clear_selected, 674	m_vertical_adjust, 680
complete_paste, 665, 666	m_zoom, 681
convert sel box to rect, 669	motion notify, 673
convert tn, 667	move selected notes, 670
convert_tn_box_to_rect, 668	move_selection_box, 670
convert_xy, 667	moving, 676
draw background on pixmap, 664	normal action, 675
draw_events_on, 669	note_off_length, 662
draw_events_on_pixmap, 664	on_button_press_event, 676
draw_progress_on_window, 664	on_button_release_event, 677
draw_selection_on_window, 664	on_enter_notify_event, 679
drop_action, 676	on_expose_event, 676
follow progress, 666	on_focus_in_event, 677
force_draw, 666	on focus out event, 678
FruitySeqRollInput, 680	on_key_press_event, 678
get_selected_box, 669	on_leave_notify_event, 679
grow_selected_notes, 672	on_motion_notify_event, 677
growing, 675	on realize, 676
horizontal_adjust, 666	on_scroll_event, 678
idle_progress, 669	on_size_allocate, 679
idle_redraw, 669	redraw, 665
m_adding, 681	redraw_events, 665
m_background_sequence, 683	reset, 665
m_cc, 684	scroll_offset_x, 674
m_chord, 681	scroll offset y, 674
m_drawing_background_seq, 684	select action, 676
m_arawing_background_seq, 004	30160t_a0tion, 070

	selecting, 675	channel_match, 745
	seqroll, 660	check_queued_tick, 710
	set_adding, 672	clear_triggers, 721
	set_background_sequence, 663	clip_timestamp, 728
	set_chord, 663	clocks_per_metronome, 706
	set_current_offset_x_y, 675	copy_events, 742
	set_data_type, 663	copy_selected, 725
	set_key, 662	copy_selected_trigger, 718
	set_note_length, 661	copy_triggers, 720
	set_scale, 662	cut_selected, 725
	set_snap, 661	cut_selected_trigger, 718
	set_zoom, 661	decrement_selected, 733
	snap_x, 667	del_selected_trigger, 718
	snap_y, 666	del_trigger, 715
	start_paste, 665	event_count, 702
	update_and_draw, 665	event_in_range, 743
	update_background, 664	EventStack, 700
	update_mouse_pointer, 672	events, 701
	update_pixmap, 663	get 32nds per quarter, 706
	update_sizes, 663	get_beat_width, 705
	vertical_adjust, 666	get_beats_per_bar, 705
	xy_to_rect, 668	get_clipboard_box, 727
sea6	4::seqtime, 684	get_editing, 707
	∼seqtime, 686	get_hold_undo, 703
	change_horz, 688	get_last_tick, 708
	draw_pixmap_on_window, 687	get_length, 708
	draw_progress_on_window, 687	get_max_trigger, 720
	idle_progress, 688	get_measures, 705
	m_ppqn, 689	get_midi_bus, 721
	m_scroll_offset_ticks, 689	get_midi_channel, 712
	m_scroll_offset_x, 689	get_minmax_note_events, 739
	m_seq, 689	get_name, 707
	_ ·	_
	m_zoom, 689 on_button_press_event, 688	get_next_event, 739, 740 get_next_note_event, 738
	on_button_release_event, 689	get_next_trigger, 740
		get_num_selected_events, 724
	on_expose_event, 688	
	on_realize, 688	get_num_selected_notes, 724
	on_size_allocate, 688	get_playing, 709
	redraw, 687	get_ppqn, 705
	reset, 687	get_quantized_rec, 711
	seqtime, 686	get_queued, 710
	set_zoom, 687	get_queued_tick, 710
	update_pixmap, 687	get_raise, 708
	update_sizes, 688	get_recording, 710
sequ	4::sequence, 689	get_selected_box, 726
	~sequence, 701	get_song_mute, 707
	add_chord, 730	get_thru, 711
	add_event, 714, 730	get_transposable, 707
	add_note, 729	get_trigger_count, 702
	add_trigger, 714	get_trigger_offset, 721
	adjust_offset, 744	get_trigger_paste_tick, 702
	adjust_timestamp, 727	get_trigger_state, 716
	adjust_trigger_offsets_to_length, 744	get_triggers, 716
	any_selected_notes, 701	grow_selected, 735
	apply_song_transpose, 707	grow_trigger, 715
	background_sequence, 742	have_redo, 703
	change_event_data_lfo, 732	have_undo, 703
	change_event_data_range, 732	increment_selected, 733

intersect_events, 718	m_triggers, 746
intersect_notes, 717	m_us_per_quarter_note, 751
intersect_triggers, 717	m_was_playing, 748
is_dirty_edit, 711	mark_selected, 736
is_dirty_main, 711	measures_to_ticks, 705
is_dirty_names, 712	mod_last_tick, 709
is_dirty_perf, 711	modify, 702
is_smf_0, 712	move_selected_notes, 728
link_new, 737	move_selected_triggers_to, 719
m_32nds_per_quarter, 750	move_triggers, 720
m_background_sequence, 751	multiply_pattern, 741
m_bus, 747	musical_key, 741
m_channel_match, 747	musical_scale, 742
m_clocks_per_metronome, 750	name, 707
m_dirty_edit, 748	note_off_margin, 743
m_dirty_main, 748	number, 702
m_dirty_names, 749	off_playing_notes, 737
m dirty perf, 749	off_queued, 709
m_editing, 749	on queued, 710
m_events, 746	operator=, 701
m_events_clipboard, 746	partial_assign, 701
m_events_redo, 747	paste_selected, 726
m_events_undo, 746	paste_trigger, 719
m_events_undo_hold, 746	pause, 738
m_have_redo, 746	perform, 745
m_have_undo, 746	play, 713
m iterator draw, 747	play_note_off, 737
m_last_tick, 749	play_note_on, 737
m_length, 750	play_queue, 713
m_masterbus, 747	pop_redo, 704
m maxbeats, 749	pop_trigger_redo, 704
m_midi_channel, 747	pop_trigger_undo, 704
m_musical_key, 751	pop_undo, 704
m_musical_scale, 751	print, 713
m_mutex, 752	print triggers, 713
m_name, 749	push_quantize, 741
m_note_off_margin, 752	push_trigger_undo, 704
m_note_off_velocity, 751	push_undo, 703
m_note_on_velocity, 751	put_event_on_bus, 743
m_notes_on, 747	quantize_events, 740
m_parent, 746	remove, 744, 745
m_playing, 748	remove_all, 745
m_playing_notes, 748	remove_marked, 736
m_ppqn, 750	remove_selected, 736
m_quantized_rec, 748	reset, 738
m_queued, 748	reset_draw_marker, 738
m_queued_tick, 749	reset_draw_trigger_marker, 738
m_raise, 749	select_action_e, 700
m_rec_vol, 751	select_all, 725
m_recording, 748	select_all_notes, 724
m_seq_number, 750	select_even_or_odd_notes, 724
m_snap_tick, 750	select_event_handle, 723
m_song_mute, 747	select_events, 722, 723
m_thru, 748	select_linked, 724
m_time_beat_width, 750	select_note_events, 722
m_time_beats_per_measure, 750	select_trigger, 716
m_transposable, 747	selected_trigger_end, 720
m_trigger_offset, 749	selected_trigger_start, 719

sequence, 701	m_tick_start, 755
set_32nds_per_quarter, 706	offset, 755
set_beat_width, 705	operator<, 753
set_beats_per_bar, 705	selected, 755
set_dirty, 712	tick_end, 754
set_dirty_mp, 712	tick_start, 754
set_editing, 707	trigger, 753
set_have_redo, 703	seq64::triggers, 756
set_have_undo, 703	\sim triggers, 760
set_hold_undo, 703	add, 762
set_last_tick, 708	adjust_offset, 770
set_length, 708	adjust_offsets_to_length, 762
set_master_midi_bus, 721	clear, 769
set_measures, 704	copy, 768
set_midi_bus, 721	copy_selected, 766
set_midi_channel, 712	FruityPerfInput, 771
set_name, 704	get_maximum, 767
set_parent, 743	get_selected_end, 767
set_playing, 709	get_selected_start, 767
set_quantized_rec, 710	get_state, 764
set_raise, 708	get_trigger_paste_tick, 770
set_rec_vol, 706	grow, 763
set_recording, 710	grow_edit_t, 759
set_snap_tick, 710	intersect, 764
set_song_mute, 706	List, 758
set_thru, 711	m_clipboard, 771
set_transposable, 707	m_iterator_draw_trigger, 771
set_trigger_offset, 744	m_iterator_play_trigger, 771
set_trigger_paste_tick, 702	m_length, 772
shift_notes, 741	m_parent, 771
show_events, 742	m_paste_tick, 772
split_trigger, 715	m_ppqn, 772
stream_event, 731	m_redo_stack, 771
stretch_selected, 735	m_trigger_copied, 771
toggle_playing, 709	m_triggers, 771
toggle_queued, 709	m_undo_stack, 771
toggle_song_mute, 707	midi_container, 770
transpose_notes, 741	midifile, 770
triggerlist, 702	move, 767
triggers, 745	move_selected, 766
trim_timestamp, 728	next, 769
unpaint_all, 736	next_trigger, 769
unselect, 736	operator=, 760
unselect_triggers, 717	paste, 766
us_per_quarter_note, 706	play, 761
verify_and_link, 736	pop_redo, 761
zero_markers, 737	pop_undo, 761
eq64::trigger, 752	print, 761
decrement_offset, 755	push_undo, 761
decrement_tick_end, 754	remove, 763
decrement_tick_start, 754	remove_selected, 766
increment_offset, 755	reset_draw_trigger_marker, 769
increment_tick_end, 754	select, 764
increment_tick_start, 754	Seq24PerfInput, 771
length, 754	sequence, 770
m_offset, 755	set_length, 760
m_selected, 756	set_ppqn, 760
m_tick_end, 755	set_trigger_paste_tick, 769

split, 763, 770	dump_summary, 799
Stack, 758	global_seq_feature, 795
triggerlist, 761	gmute_tracks, 793
triggers, 760	grid_brackets, 793, 797
unselect, 764	grid_is_black, 793
seq64::user_instrument, 772	grid_is_normal, 793
controller_active, 775	grid_is_white, 793
controller_count, 774	grid_style, 792, 797
controller max, 774	instrument, 791
controller name, 774	instrument_controller_active, 792
copy_definitions, 776	instrument_controller_name, 792
is_valid, 774	instrument_count, 791
m_controller_count, 776	instrument_name, 792
m_instrument_def, 776	InstrumentConstIterator, 789
m_is_valid, 776	InstrumentIterator, 789
	Instruments, 789
name, 774	
operator=, 773	inverse_colors, 797, 801
set_controller, 775	m_allow_two_perfedits, 805
set_defaults, 774	m_control_height, 804
set_name, 775	m_current_zoom, 804
user_instrument, 773	m_global_seq_feature_save, 804
seq64::user_instrument_t, 776	m_gmute_tracks, 808
controllers, 777	m_grid_brackets, 803
controllers_active, 777	m_grid_style, 803
instrument, 777	m_h_perf_page_increment, 806
seq64::user_midi_bus, 777	m_instruments, 803
channel_count, 779	m_inverse_colors, 806
channel_max, 779	m_mainwid_border, 804
copy_definitions, 780	m_mainwid_spacing, 804
instrument, 779	m_mainwid_x, 809
is_valid, 779	m_mainwid_y, 809
m_channel_count, 780	m_mainwnd_cols, 804
m is valid, 780	m_mainwnd_rows, 803
m midi bus def, 780	m max sequence, 809
name, 779	m_max_sets, 804
operator=, 778	m_midi_beat_width, 808
set_defaults, 779	m_midi_beats_per_measure, 807
set instrument, 780	m_midi_beats_per_minute, 808
set name, 780	m_midi_buses, 803
user midi bus, 778	m_midi_buss_override, 808
seq64::user_midi_bus_t, 781	m midi ppqn, 807
alias, 781	m_progress_bar_colored, 806
instrument, 781	m progress bar thick, 806
seg64::user settings, 781	m save user config, 810
add_bus, 790	m_seqarea_seq_x, 809
add_instrument, 790	m_seqarea_seq_y, 809
allow_two_perfedits, 796, 800	m_seqarea_x, 809
baseline_ppqn, 800	m_seqarea_y, 809
bus, 791	m_seqchars_x, 807
bus_count, 791	m_seqchars_y, 807
bus_instrument, 791	m_seqedit_bgsequence, 805
bus_name, 791	m_seqedit_key, 805
BussConstIterator, 789	m_seqedit_scale, 805
BussIterator, 789	m_seqs_in_set, 808
Busses, 789	m_text_x, 807
control_height, 795, 799	m_text_y, 807
controller_active, 792	m_total_seqs, 808
controller_name, 792	m_use_more_icons, 806

m_use_new_font, 805	seq_clear_perf
m_v_perf_page_increment, 806	seq_clear_perr seq64::seqmenu, 653
m_window_redraw_rate_ms, 806	seg copy
mainwid_border, 794, 799	seq64::seqmenu, 652
mainwid_grid_style_t, 789	seq_cut
mainwid_spacing, 794, 799	seq64::seqmenu, 652
mainwid_x, 795	seq_edit
mainwid_y, 795	seq64::seqmenu, 651
mainwnd_cols, 793, 797	seg event edit
mainwnd_cois, 700, 707	seq64::seqmenu, 651
max_sequence, 793	seg event type t
max_sets, 793, 798	seq64, 55
max_zoom, 800	seq_from_xy
mc_baseline_ppqn, 810	seq64::mainwid, 330
mc_max_zoom, 810	seq_in_playing_screen
mc_min_zoom, 810	seq64::perform, 510
midi_beat_width, 800, 802	seq_modifier_t
midi_beats_per_bar, 799, 802	seq64, 54
midi_beats_per_minute, 800, 802	seq_new
midi buss override, 800, 801	seq64::seqmenu, 652
midi_ppqn, 799, 801	seq_number_size
min_zoom, 800	seq_namber_size seq64::midifile, 420
normalize, 790	seq paste
operator=, 790	seq_paste seq64::seqmenu, 652
perf_h_page_increment, 796, 800	seq_scroll_direction_t
perf_v_page_increment, 796, 801	seq_scroll_direction_t seq64, 55
private_bus, 802	seq_set_and_edit
private_instrument, 802	seq_set_and_edit seq64::mainwid, 328
progress_bar_colored, 796, 801	seq64::seqmenu, 651
progress_bar_thick, 796, 801	seq_set_and_eventedit
save_user_config, 797	seq_set_and_evernedit seq64::mainwid, 328
segarea_seg_x, 794, 799	seq64::seqmenu, 652
seqarea_seq_x, 794, 799	segarea seg x
seqarea_x, 794, 798	seq64::user_settings, 794, 799
seqarea y, 794, 798	segarea seg y
seqchars_x, 794, 798	seq64::user_settings, 794, 799
seqchars y, 794, 798	
sequit_bgsequence, 796	seqarea_x seq64::user_settings, 794, 798
sequent_bgsequence, 790	sequea_y
sequent_key, 790 sequent_scale, 795	seq64::user settings, 794, 798
seqs_in_set, 793	sequalities settings, 794, 790
set_bus_instrument, 791	seq64::user settings, 794, 798
set_bus_instrument, 791	sequal sequal sequences sequences y
	seq64::user settings, 794, 798
set_instrument_controllers, 791	
text_x, 794, 798	seqdata
text_y, 794, 798	seq64::seqdata, 585
use_more_icons, 797, 801	seqedit
use_new_font, 796, 800	seq64::seqedit, 601
user_settings, 790	seqedit_bgsequence
userfile, 803	seq64::user_settings, 796
window_redraw_rate, 797, 801	seqedit_key
zoom, 795	seq64::user_settings, 796
64::userfile, 811	seqedit_scale
~userfile, 812	seq64::user_settings, 795
dump_setting_summary, 813	seqevent
parse, 812	seq64::seqdata, 591
userfile, 812	seq64::seqevent, 625
write, 812	seqkeys

seq64::seqkeys, 638	seq64::perform, 515
seqmenu	set_alsa_client_id
seq64::seqedit, 612	seq64::lash, 312
seq64::seqmenu, 649	set_and_copy_mute_group
seqroll	seq64::perform, 506
seq64::seqdata, 591	set_background_sequence
seq64::seqkeys, 644	seq64::seqedit, 605
seq64::seqroll, 660	seq64::seqroll, 663
seqs_in_set	set_beat_width
seq64::user_settings, 793	seq64::jack_assistant, 253
seqspec_string	seq64::perfedit, 442
seq64::editable_event, 125	seq64::perform, 474
seqtime	seq64::seqedit, 602
seq64::seqtime, 686	seq64::sequence, 705
sequence	set_beats_per_bar
seq64::event_list, 165	seq64::perfedit, 442
seq64::sequence, 701	seq64::perform, 474
seq64::triggers, 770	seq64::seqedit, 602
sequence_count	seq64::sequence, 705
seq64::perform, 472	set_beats_per_measure
sequence_key	seq64::jack_assistant, 253
seq64::mainwnd, 345	set_beats_per_minute
seq64::perform, 495	seq64::jack_assistant, 253
sequence_label	seq64::mastermidibus, 357
seq64::perform, 495	seq64::perform, 509
sequence_max	set_bus_and_midi_channel
seq64::perform, 472	seq64::seqmenu, 653
sequence_playing_change	set_bus_instrument
seq64::perform, 485	seq64::user_settings, 791
sequence_playing_off	set_channel
seq64::perform, 485	seq64::event, 146
sequence_playing_on	set_chord
seq64::perform, 485	seq64::seqedit, 605
sequence_playing_toggle	seq64::seqroll, 663
seq64::perform, 485	set_clock
session_event	seq64::mastermidibus, 363
seq64::jack_assistant, 255	seq64::midibus, 400
set	set_clock_mod
seq64::keybindentry, 273	seq64::midibus, 401
seq64::midi_control, 376, 377	set_config_files
set_32nds_per_quarter	seq64::rc_settings, 569
seq64::perform, 474	set_controller
seq64::sequence, 706	seq64::user_instrument, 775
set_active	set_current_drop_x
seq64::perform, 508	seq64::gui_drawingarea_gtk2, 231
set_adding	set_current_drop_y
seq64::AbstractPerfInput, 103	seq64::gui_drawingarea_gtk2, 231
seq64::Seq24SeqEventInput, 581	set_current_event
seq64::seqroll, 672	seq64::eventslots, 185
set_adding_pressed	set_current_offset_x_y
seq64::AbstractPerfInput, 104	seq64::seqroll, 675
set_all_key_events	set_data
seq64::keys_perform, 292	seq64::event, 147
seq64::keys_perform_gtk2, 302	set_data_type
seq64::perform, 515	seq64::seqdata, 586
set_all_key_groups	seq64::seqedit, 607
seq64::keys_perform, 292	seq64::seqevent, 626
seq64::keys_perform_gtk2, 302	seq64::seqroll, 663

set_defaults	set_jack_mode
seq64::rc_settings, 563	seq64::jack_assistant, 258
seq64::user_instrument, 774	seq64::perfedit, 442
seq64::user_midi_bus, 779	seq64::perform, 476
seq64::user_settings, 790	set_jack_running
set_dirty	seq64::jack_assistant, 259
seq64::eventedit, 172	set_jack_stop_tick
seq64::sequence, 712	seq64::jack_assistant, 258
set_dirty_mp	seq64::perform, 477
seq64::sequence, 712	set jack tick
set_edit_sequence	seq64::perform, 482
seq64::perform, 473	set_key
seq64::seqmenu, 649	seq64::seqedit, 605
set_editing	seq64::seqkeys, 639
seq64::sequence, 707	seq64::seqroll, 662
set_event_category	set_key_event
seq64::eventedit, 171	seq64::keys_perform, 292
·	
set_event_data_0 seq64::eventedit, 172	seq64::perform, 515
•	set_key_group
set_event_data_1	seq64::keys_perform, 293
seq64::eventedit, 172	seq64::perform, 515
set_event_name	set_keys
seq64::eventedit, 172	seq64::keys_perform, 282
set_event_timestamp	set_last_tick
seq64::eventedit, 172	seq64::sequence, 708
set_follow_transport	set_left_tick
seq64::jack_assistant, 258	seq64::perform, 482
seq64::perfedit, 441	set_length
seq64::perform, 478	seq64::sequence, 708
set_group_mute_state	seq64::triggers, 760
seq64::perform, 487	set_line
set_guides	seq64::gui_drawingarea_gtk2, 221
seq64::perfedit, 443	set_listen_button_press
seq64::perfroll, 535	seq64::seqkeys, 640
seq64::perftime, 552	set_listen_button_release
set_have_redo	seq64::seqkeys, 640
seq64::perform, 501	set_listen_motion_notify
seq64::sequence, 703	seq64::seqkeys, 640
set_have_undo	set_looped
seq64::perform, 500	seq64::perfedit, 443
seg64::sequence, 703	set looping
set_hint_key	seq64::perform, 509
seq64::seqkeys, 639	set_master_midi_bus
set hint state	seq64::sequence, 721
seq64::seqkeys, 639	set measures
set_hold_undo	seq64::seqedit, 604
seq64::sequence, 703	seq64::sequence, 704
set_image	set_midi_bus
_ ·	
seq64::perfedit, 444	seq64::seqedit, 605
set_input	seq64::sequence, 721
seq64::mastermidibus, 363	set_midi_channel
seq64::midibus, 401	seq64::seqedit, 604
set_input_bus	seq64::sequence, 712
seq64::perform, 496	set_mode_group_learn
set_instrument	seq64::perform, 505
seq64::user_midi_bus, 780	set_mode_group_mute
set_instrument_controllers	seq64::perform, 505
seq64::user_settings, 791	set_name

seq64::sequence, 704	set_seq_count
seq64::user_instrument, 775	seq64::eventedit, 171
seq64::user_midi_bus, 780	set_seq_ppqn
set_note	seq64::eventedit, 171
seq64::event, 150	set_seq_time_sig
set_note_length	seq64::eventedit, 171
seq64::seqedit, 602	set_seq_title
seq64::seqroll, 661	seq64::eventedit, 171
set_note_velocity	set_sequence_control_status
seq64::event, 151	seq64::perform, 484
set_offset	set_sequence_input
seq64::perform, 488	seq64::mastermidibus, 361
set_orig_ticks	set_snap
seq64::perform, 509	seq64::perfedit, 443
set_parent	seq64::seqedit, 601
seq64::sequence, 743	seq64::seqevent, 626
set_play_image	seq64::seqroll, 661
seq64::mainwnd, 343	set_snap_tick
set_playback_mode	seq64::sequence, 710
seq64::perform, 512	set_song_mute
set_playing	seq64::mainwnd, 346
seq64::sequence, 709	seq64::perform, 505
set_playing_screenset	seq64::sequence, 706
seq64::keys_perform, 285	set_songlive_image
seq64::perform, 504	seq64::mainwnd, 343
set_position	set_start_from_perfedit
seq64::jack_assistant, 263	seq64::jack_assistant, 259
set_ppqn	set_start_tick
seq64::jack_assistant, 257	seq64::perform, 483
seq64::mastermidibus, 357	set_status
seq64::perfroll, 537 seq64::perftime, 553	seq64::event, 145, 146
seq64::triggers, 760	set_status_from_string
set_quantized_rec	seq64::editable_event, 124 set status keep channel
seq64::sequence, 710	seq64::event, 146
set raise	set_sysex_size
seq64::sequence, 708	seq64::event, 149
set_rec_vol	sequal.event, 149 set_text
seq64::seqedit, 603	seq64::eventslots, 188
seq64::sequence, 706	set_thru
set recording	seq64::sequence, 711
seq64::sequence, 710	set timestamp
set reposition	seg64::event, 142
seq64::perform, 478	set_transposable
set_right_tick	seq64::segmenu, 653
seq64::perform, 483	seq64::sequence, 707
set running	set_transpose
seq64::perform, 512	seq64::perfedit, 442
set_scale	seq64::perform, 484
seq64::perftime, 552	set_transpose_image
seq64::seqedit, 605	seq64::seqedit, 602
seq64::seqkeys, 639	set_trigger_offset
seq64::seqroll, 662	seq64::sequence, 744
set_screen_set_notepad	set_trigger_paste_tick
seq64::perform, 503, 504	seq64::sequence, 702
set_screenset	seq64::triggers, 769
seq64::mainwid, 327	set_was_active
seq64::perform, 500	seq64::perform, 508
1 1 - /	

set_zoom	seq64::jack_assistant, 266
seq64::perfedit, 441	sm_system_event_names
seq64::perfroll, 539	seq64::editable_event, 126
seq64::perftime, 553	snap_x
seq64::seqdata, 586	seq64::perfroll, 538
seq64::seqedit, 601	seq64::seqevent, 630
seq64::seqevent, 626	seq64::seqroll, 667
seq64::seqroll, 661	snap_y
seq64::seqtime, 687	seq64::seqevent, 629
shift_lock	seq64::seqroll, 666
seq64::keystroke, 309	snapshot_1
shift_notes	seq64::keys_perform, 284
seq64::sequence, 741	snapshot_2
shorten_file_spec	seq64::keys_perform, 284
seq64, 64	song_fill_seq_event
show_events	seq64::midi_container, 373
seq64::sequence, 742	song_fill_seq_trigger
show_midi	seq64::midi_container, 374
seq64::rc_settings, 564, 567	song_mode
show_position	seq64::keys_perform, 288
seq64::jack_assistant, 261	song_start_mode
show_statuses	seq64::jack_assistant, 258
seq64::jack_assistant, 261	seq64::perform, 476
show_ui_sequence_key	split
seq64::keys_perform, 290	seq64::midi_splitter, 386
seq64::perform, 489	seq64::triggers, 763, 770
show_ui_sequence_number	split_channel
seq64::keys_perform, 290	seq64::midi_splitter, 387
seq64::perform, 490	split_trigger
signal	seq64::perform, 501
seq64::condition_var, 111	seq64::perfroll, 539
signal_action	seq64::sequence, 715
seq64::mainwnd, 348	Stack
size	seq64::triggers, 758
seq64::midi_container, 370	start
seq64::midi_list, 381	seq64::jack_assistant, 255
seq64::midi_vector, 394	seq64::keys_perform, 286
SlotMap	seq64::lash, 312
seq64::keys_perform, 281	seq64::mastermidibus, 359
sm_category_arrays	seq64::midibus, 400
seq64::editable_event, 127	seq64::perform, 506
sm_category_names	start_from_perfedit
seq64::editable_event, 126	seq64::perform, 478
sm_channel_event_names	start_jack
seq64::editable_event, 126	seq64::perform, 507
sm_cond	start_key
seq64::condition_var, 112	seq64::perform, 492
sm_internal_keys	start_paste
seq64::gui_assistant_gtk2, 216	seq64::seqevent, 629
sm_mc_dummy	seq64::seqroll, 665
seq64::perform, 519	start_playing
sm_meta_event_names	seq64::mainwnd, 344
seq64::editable_event, 126	seq64::perfedit, 445
sm_prop_event_names	seq64::perform, 491
seq64::editable_event, 127	seq64::seqedit, 609
sm_recursive_mutex	stats
seq64::mutex, 424 sm_status_pairs	seq64::rc_settings, 564, 567 status
οπ_οιαίμο_μαπο	วเสเนจ

seq64::midi_control, 376	tick_multiplier
status_string	seq64::jack_assistant, 259
seq64::editable_event, 125	tick_offset
stock_event_string	seq64::perftime, 554
seq64::editable_event, 125	tick_start
stop	seq64::trigger, 754
seq64::jack_assistant, 255	tick_to_pixel
seq64::keys_perform, 287	seq64::perftime, 554
seq64::mastermidibus, 359	ticks_to_delta_time_us
seq64::midibus, 400	seq64, <mark>68</mark>
seq64::perform, 506	time_as_measures
stop_jack	seq64::editable_event, 124
seq64::perform, 507	time_as_minutes
stop_key	seq64::editable_event, 124
seq64::perform, 493	time_as_pulses
stop_playing	seq64::editable_event, 124
seq64::mainwnd, 344	timeout
seq64::perfedit, 445	seq64::mainwid, 330
seq64::perform, 492	seq64::perfedit, 444
seq64::seqedit, 609	seq64::seqedit, 609
stream_event	timer_callback
seq64::sequence, 731 stretch_selected	seq64::mainwnd, 343
seq64::sequence, 735	timestamp
string_is_void	seq64::editable_event, 123
seq64, 64	timestamp_format_t
string_not_void	seq64::editable_event, 120
seq64, 64	timestamp_string
•	seq64::editable_event, 123
string_to_midibyte	timestring_to_pulses
seq64, 62 string_to_pulses	seq64, 61
seq64, 62	timing
seq64::editable_events, 132	seq64::editable_events, 132
strings_match	to_string
seq64, 65	seq64, <mark>73</mark>
sync	toLower
seq64::jack_assistant, 262	seq64::mainwnd, 345
sysex	toggle_all_tracks
seq64::mastermidibus, 362	seq64::perform, 486
seq64::midibus, 399	seq64::seqmenu, 653
SysexContainer	toggle_current_sequence
seq64::event, 140	seq64::seqmenu, 651
,,	toggle_follow_transport
tap_bpm	seq64::jack_assistant, 258
seq64::keys_perform, 289	seq64::perfedit, 441
tempo_to_us	seq64::perform, 478
seq64, 67	toggle_jack
tempo_us_from_beats_per_minute	seq64::keys_perform, 289
seq64, 67	seq64::perfedit, 441
tempo_us_to_bytes	toggle_jack_mode
seq64, 66	seq64::jack_assistant, 257
text_x	seq64::perform, 476
seq64::user_settings, 794, 798	toggle_mutes
text_y	seq64::keys_perform, 289
seq64::user_settings, 794, 798	toggle_playing
thru_change_callback	seq64::mainwnd, 344
seq64::seqedit, 606	seq64::perfedit, 445
tick_end	seq64::sequence, 709
seq64::trigger, 754	toggle_playing_tracks

seq64::perform, 486	unpaint_all
toggle_queued	seq64::event_list, 163
seq64::sequence, 709	seq64::sequence, 736
toggle_song_mute	unselect
seq64::sequence, 707	seq64::event, 150
toggle_song_start_mode	seq64::sequence, 736
seq64::jack_assistant, 258	seq64::triggers, 764
seq64::perform, 475	unselect_all
toggle_visible	seq64::event_list, 164
seq64::lfownd, 315	unselect_triggers
top_index	seq64::sequence, 717
seq64::eventslots, 184	unset_edit_sequence
track_end_size	seq64::perform, 473
seq64::midifile, 420	seq64::seqmenu, 650
track_name_size	unset_mode_group_learn
seq64::midifile, 419	seq64::perform, 506
transport_callback	unset_mode_group_mute
seq64::options, 428	seq64::perform, 505
transport_not_starting	unset_sequence_control_status
seq64::jack_assistant, 254	seq64::perform, 485
transport_state	update_all_windows
seq64::jack_assistant, 254	seq64::seqedit, 607
transpose_button_callback	update_and_draw
seq64::perfedit, 442	seq64::seqroll, 665
transpose_change_callback	update_background
seq64::seqedit, 606	seq64::seqroll, 664
transpose_note	update_mainwid_sequences
seq64::event, 151	seq64, 83
transpose_notes	seq64::mainwid, 333
seq64::sequence, 741	update_markers
trigger	seq64::mainwid, 328
seq64::trigger, 753	update_mouse_pointer
triggerlist	seq64::FruityPerfInput, 204
seq64::sequence, 702	seq64::FruitySeqEventInput, 207
seq64::triggers, 761	seq64::FruitySeqRollInput, 210
triggers	seq64::seqroll, 672
seq64::sequence, 745	update_perfedit_sequences
seq64::triggers, 760	seq64, 83
trim_timestamp	seq64::perfedit, 446
seq64::sequence, 728	update_pixmap
type	seq64::perftime, 554
seq64::keybindentry, 272	seq64::seqdata, 587
	seq04::sequala, 307 seq64::seqevent, 627
undo	seq64::seqkeys, 640
seq64::perfedit, 444	seq64::seqroll, 663
undo_callback	seq64::seqtime, 687
seq64::seqedit, 606	· · · · · · · · · · · · · · · · · · ·
unlock	update_sequences_on_window
seq64::mutex, 424	seq64::mainwid, 327
unmark	update_sizes
seq64::event, 150	seq64::perfroll, 535
unmark_all	seq64::perftime, 554
seq64::event_list, 163	seq64::seqdata, 587
unmodify	seq64::seqevent, 626
seq64::event_list, 160	seq64::seqkeys, 641
unmute_all_tracks	seq64::seqroll, 663
seq64::seqmenu, 653	seq64::seqtime, 688
unpaint	update_window_title
seq64::event, 149	seq64::mainwnd, 345

us_per_quarter_note	seq64::gui_palette_gtk2, 240
seq64::perform, 474, 475	width
seq64::sequence, 706	seq64::gui_drawingarea_gtk2::rect, 576
use_more_icons	seq64::rect, 575
seq64::user_settings, 797, 801	window_redraw_rate
use new font	seq64::user_settings, 797, 801
seq64::user_settings, 796, 800	window x
user filename	seq64::gui_drawingarea_gtk2, 220
seq64::rc_settings, 566, 570	window_y
user_filename_alt	seq64::gui_drawingarea_gtk2, 220
seq64::rc_settings, 566, 570	with_jack
user_filespec	seq64::rc settings, 565
seq64::rc_settings, 563	with_jack_master
user instrument	seq64::rc_settings, 564, 567
-	
seq64::user_instrument, 773	with_jack_master_cond
user_midi_bus	seq64::rc_settings, 564, 567
seq64::user_midi_bus, 778	with_jack_transport
user_settings	seq64::rc_settings, 564, 567
seq64::user_settings, 790	write
userfile	seq64::configfile, 114
seq64::user_settings, 803	seq64::midifile, 408
seq64::userfile, 812	seq64::optionsfile, 433
usr	seq64::userfile, 812
seq64, 81	write_byte
	seq64::midifile, 414
v_adjustment	write_header
seq64::eventedit, 173	seq64::midifile, 416
valid_midi_control_seq	write_long
seq64::perform, 511	seq64::midifile, 413
valid_sequence	write_options_files
seq64::mainwid, 329	seq64, 73
value_to_name	write_prop_header
seq64::editable_event, 121	seq64::midifile, 417
varinum_size	write_proprietary_track
seq64::midifile, 418	seq64::midifile, 417
verify_and_link	write seq number
seq64::event_list, 162	seq64::midifile, 415
seq64::sequence, 736	•
versiontext	write_short
	seq64::midifile, 414
seq64, 95	write_song
vertical_adjust	seq64::midifile, 409
seq64::perfroll, 541	write_track
seq64::seqedit, 603	seq64::midifile, 420
seq64::seqroll, 666	write_track_end
vertical_set	seq64::midifile, 416
seq64::perfroll, 541	write_track_name
seq64::seqedit, 604	seq64::midifile, 415
	write_varinum
wait	seq64::midifile, 414
seq64::condition_var, 111	
wave_func	X
seq64, 71	seq64::click, 108
wave_type_t	seq64::gui_drawingarea_gtk2::rect, 576
seq64, 54	seq64::rect, 575
white	x_to_w
seq64::gui_palette_gtk2, 239	seq64::seqevent, 628
white_key	xy_to_rect
seq64::gui_palette_gtk2, 240	seq64::seqdata, 587
white_paint	seq64::seqroll, 668

```
y
seq64::click, 109
seq64::gui_drawingarea_gtk2::rect, 576
seq64::rect, 575

yellow
seq64::gui_palette_gtk2, 240

zero_markers
seq64::sequence, 737
zoom
seq64::user_settings, 795
zoom_check
seq64::perfedit, 440
zoom_power_of_2
seq64, 66
```